

BEA Tuxedo®

ATMI C Function Reference

Copyright

Copyright © 2003 BEA Systems, Inc. All Rights Reserved.

Restricted Rights Legend

This software and documentation is subject to and made available only pursuant to the terms of the BEA Systems License Agreement and may be used or copied only in accordance with the terms of that agreement. It is against the law to copy the software except as specifically allowed in the agreement. This document may not, in whole or in part, be copied photocopied, reproduced, translated, or reduced to any electronic medium or machine readable form without prior consent, in writing, from BEA Systems, Inc.

Use, duplication or disclosure by the U.S. Government is subject to restrictions set forth in the BEA Systems License Agreement and in subparagraph (c)(1) of the Commercial Computer Software-Restricted Rights Clause at FAR 52.227-19; subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.227-7013, subparagraph (d) of the Commercial Computer Software--Licensing clause at NASA FAR supplement 16-52.227-86; or their equivalent.

Information in this document is subject to change without notice and does not represent a commitment on the part of BEA Systems. THE SOFTWARE AND DOCUMENTATION ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND INCLUDING WITHOUT LIMITATION, ANY WARRANTY OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. FURTHER, BEA Systems DOES NOT WARRANT, GUARANTEE, OR MAKE ANY REPRESENTATIONS REGARDING THE USE, OR THE RESULTS OF THE USE, OF THE SOFTWARE OR WRITTEN MATERIAL IN TERMS OF CORRECTNESS, ACCURACY, RELIABILITY, OR OTHERWISE.

Trademarks or Service Marks

BEA, Jolt, Tuxedo, and WebLogic are registered trademarks of BEA Systems, Inc. BEA Builder, BEA Campaign Manager for WebLogic, BEA eLink, BEA Liquid Data for WebLogic, BEA Manager, BEA WebLogic Commerce Server, BEA WebLogic Enterprise, BEA WebLogic Enterprise Platform, BEA WebLogic Express, BEA WebLogic Integration, BEA WebLogic Personalization Server, BEA WebLogic Platform, BEA WebLogic Portal, BEA WebLogic Server, BEA WebLogic Workshop and How Business Becomes E-Business are trademarks of BEA Systems, Inc.

All other trademarks are the property of their respective companies.

Contents

About This Document	
What You Need to Know	vi
e-docs Web Site	vi
How to Print the Document	vii
Related Information	vii
Contact Us!	vii
Documentation Conventions	iz
Section 3c - C Functions	
Introduction to the C Language Application-to-Transaction Monitor	Interface 1-7
AEMsetblockinghook(3c)	1-43
AEOaddtypesw(3c)	1-45
AEPisblocked(3c)	1-48
AEWsetunsol(3c)	1-49
buffer(3c)	1-50
catgets(3c)	1-60
catopen, catclose(3c)	1-61
decimal(3c)	1-63
getURLEntityCacheDir(3c)	1-66
GetURLEntityCaching(3c)	1-67
gp_mktime(3c)	1-68
nl_langinfo(3c)	1-72
rpc_sm_allocate, rpc_ss_allocate(3c)	1-73
rpc_sm_client_free, rpc_ss_client_free(3c)	1-75
rpc_sm_disable_allocate, rpc_ss_disable_allocate(3c)	1-77
rpc_sm_enable_allocate, rpc_ss_enable_allocate(3c)	1-78
rpc_sm_free, rpc_ss_free(3c)	1-79

rpc_sm_set_client_alloc_free, rpc_ss_set_client_alloc_free(3c)1-8	0
<pre>rpc_sm_swap_client_alloc_free, rpc_ss_swap_client_alloc_free(3c) 1-82</pre>	•
setlocale(3c)	4
setURLEntityCacheDir(3c)1-8	6
setURLEntityCaching(3c)1-8	7
strerror(3c)	8
strftime(3c) 1-8	9
tpabort(3c)	2
tpacall(3c) 1-9	4
tpadmcall(3c)1-9	7
tpadvertise(3c)1-10	0
tpalloc(3c)1-10.	2
tpbegin(3c)1-10-	4
tpbroadcast(3c) 1-10	6
tpcall(3c)1-10	9
tpcancel(3c)	4
tpchkauth(3c)1-11	5
tpchkunsol(3c)1-11	7
tpclose(3c)	9
tpcommit(3c)	0
tpconnect(3c)1-12	3
tpconvert(3c)	7
tpconvmb(3c)	9
tpcryptpw(3c) 1-13	1
tpdequeue(3c)	3
tpdiscon(3c)1-14	3
tpenqueue(3c) 1-14	5
tpenvelope(3c)1-15	6
tperrordetail(3c)1-16	0
tpexport(3c)	3
tpforward(3c)1-16	5
tpfree(3c)1-16	8
tpgetadmkey(3c)1-16	9
tngetctxt(3c) 1-17	0

tpgetlev(3c)	1-172
tpgetmbenc(3c)	1-173
tpgetrply(3c)	1-174
tpgprio(3c)	1-179
tpimport(3c)	1-181
tpinit(3c)	1-183
tpkey_close(3c)	1-192
tpkey_getinfo(3c)	1-193
tpkey_open(3c)	1-196
tpkey_setinfo(3c)	1-199
tpnotify(3c)	1-200
tpopen(3c)	1-203
tppost(3c)	1-204
tprealloc(3c)	1-208
tprecv(3c)	1-210
tpresume(3c)	1-215
tpreturn(3c)	1-217
tpscmt(3c)	1-221
tpseal(3c)	1-224
tpsend(3c)	1-225
tpservice(3c)	1-230
tpsetctxt(3c)	1-233
tpsetmbenc(3c)	1-235
tpsetunsol(3c)	1-236
tpsign(3c)	1-238
tpsprio(3c)	1-239
tpstrerror(3c)	1-241
tpstrerrordetail(3c)	1-242
tpsubscribe(3c)	1-244
tpsuspend(3c)	1-253
tpsvrdone(3c)	1-255
tpsvrinit(3c)	1-256
tpsvrthrdone(3c)	
tpsvrthrinit(3c)	1-259
tpterm(3c)	1-261

tptypes(3c)	1-264
tpunadvertise(3c)	1-265
tpunsubscribe(3c)	1-267
TRY(3c)	1-270
tuxgetenv(3c)	1-278
tuxgetmbaconv(3c)	1-279
tuxgetmbenc(3c)	1-280
tuxputenv(3c)	1-281
tuxreadenv(3c)	1-282
tuxsetmbaconv(3c)	1-285
tuxsetmbenc(3c)	1-286
tx_begin(3c)	1-287
tx_close(3c)	1-289
tx_commit(3c)	1-291
tx_info(3c)	1-294
tx_open(3c)	1-296
tx_rollback(3c)	1-298
tx_set_commit_return(3c)	1-300
tx_set_transaction_control(3c)	1-302
tx_set_transaction_timeout(3c)	1-304
userlog(3c)	1-306
Usignal(3c)	1-309
Uunix_err(3c)	1-312

About This Document

This document provides reference information on C language functions used in the BEA Tuxedo ATMI environment. The reference pages are arranged in alphabetical order by function name.

What You Need to Know

This document is intended for the following audiences:

- administrators who are interested in configuring and managing applications in a BEA Tuxedo environment
- application developers who are interested in programming applications in a BEA
 Tuxedo environment

This document assumes a familiarity with the BEA Tuxedo platform and C programming.

e-docs Web Site

BEA product documentation is available on the BEA corporate Web site. From the BEA Home page, click on Product Documentation or go directly to the "e-docs" Product Documentation page at http://e-docs.bea.com.

How to Print the Document

You can print a copy of this document from a Web browser, one file at a time, by using the File—>Print option on your Web browser.

A PDF version of this document is available on the BEA Tuxedo documentation Home page on the e-docs Web site (and also on the documentation CD). You can open the PDF in Adobe Acrobat Reader and print the entire document (or a portion of it) in book format. To access the PDFs, open the BEA Tuxedo documentation Home page, click the PDF files button and select the document you want to print.

If you do not have the Adobe Acrobat Reader, you can get it for free from the Adobe Web site at http://www.adobe.com/.

Related Information

Related documents are listed in the See Also section of each reference page.

Contact Us!

Your feedback on the BEA Tuxedo documentation is important to us. Send us e-mail at **docsupport@bea.com** if you have questions or comments. Your comments will be reviewed directly by the BEA professionals who create and update the BEA Tuxedo documentation.

In your e-mail message, please indicate that you are using the documentation for the BEA Tuxedo 8.0 release.

If you have any questions about this version of BEA Tuxedo, or if you have problems installing and running BEA Tuxedo, contact BEA Customer Support through BEA WebSupport at **www.bea.com**. You can also contact Customer Support by using the contact information provided on the Customer Support Card, which is included in the product package.

When contacting Customer Support, be prepared to provide the following information:

- Your name, e-mail address, phone number, and fax number
- Your company name and company address
- Your machine type and authorization codes
- The name and version of the product you are using
- A description of the problem and the content of pertinent error messages

Documentation Conventions

The following documentation conventions are used throughout this document.

Convention	Item
boldface text	Indicates terms defined in the glossary.
Ctrl+Tab	Indicates that you must press two or more keys simultaneously.
italics	Indicates emphasis or book titles.

Convention	Item
monospace text	Indicates code samples, commands and their options, data structures and their members, data types, directories, and file names and their extensions. Monospace text also indicates text that you must enter from the keyboard.
	Examples:
	<pre>#include <iostream.h> void main () the pointer psz</iostream.h></pre>
	chmod u+w *
	\tux\data\ap
	.doc
	tux.doc
	BITMAP
	float
monospace Identifies significant words in code.	
boldface	Example:
text	void commit ()
monospace	Identifies variables in code.
italic	Example:
text	String expr
UPPERCASE	Indicates device names, environment variables, and logical operators.
TEXT	Examples:
	LPT1
	SIGNON
	OR
{ }	Indicates a set of choices in a syntax line. The braces themselves should never be typed.
[]	Indicates optional items in a syntax line. The brackets themselves should never be typed.
	Example:
	<pre>buildobjclient [-v] [-o name] [-f file-list] [-l file-list]</pre>
I	Separates mutually exclusive choices in a syntax line. The symbol itself should never be typed.

Convention	Item	
	Indicates one of the following in a command line:	
	■ That an argument can be repeated several times in a command line	
	■ That the statement omits additional optional arguments	
	■ That you can enter additional parameters, values, or other information	
	The ellipsis itself should never be typed.	
	Example:	
	<pre>buildobjclient [-v] [-o name] [-f file-list] [-l file-list]</pre>	
	Indicates the omission of items from a code example or from a syntax line. The vertical ellipsis itself should never be typed.	

Section 3c - C Functions

Table 1 BEA Tuxedo ATMI C Functions

Name	Description
Introduction to the C Language Application-to-Transaction Monitor Interface	Provides an introduction to the C language ATMI
AEMsetblockinghook(3c)	Establishes an application-specific blocking hook function
AEOaddtypesw(3c)	Installs or replaces a user-defined buffer type at execution time
AEPisblocked(3c)	Determines if a blocking call is in progress
AEWsetunsol(3c)	Posts Windows message for BEA Tuxedo ATMI unsolicited event
buffer(3c)	Semantics of elements in tmtype_sw_t
catgets(3c)	Reads a program message
catopen, catclose(3c)	Opens/closes a message catalogue
decimal(3c)	Decimal conversion and arithmetic routines
getURLEntityCacheDir(3c)	Gets the absolute path to the location where the DTD, schemas, and Entity files are cached
GetURLEntityCaching(3c)	Gets the chaching mechanism for the DTD, schemas, and Entity files
gp_mktime(3c)	Converts a tm structure to a calendar time
nl_langinfo(3c)	Language information
<pre>rpc_sm_allocate, rpc_ss_allocate(3c)</pre>	Allocates memory within the RPC stub

Table 1 BEA Tuxedo ATMI C Functions (Continued)

Name	Description
<pre>rpc_sm_client_free, rpc_ss_client_free(3c)</pre>	Frees memory returned from a client stub
<pre>rpc_sm_disable_allocate, rpc_ss_disable_allocate(3c)</pre>	Releases resources and allocated memory within the stub memory management scheme
<pre>rpc_sm_enable_allocate, rpc_ss_enable_allocate(3c)</pre>	Enables the stub memory management environment
rpc_sm_free, rpc_ss_free(3c)	Frees memory allocated by the rpc_sm_allocate() routine
<pre>rpc_sm_set_client_alloc_free, rpc_ss_set_client_alloc_free(3c)</pre>	Sets the memory allocation and freeing mechanisms used by the client stubs
<pre>rpc_sm_swap_client_alloc_free, rpc_ss_swap_client_alloc_free(3c)</pre>	Exchanges current memory allocation and freeing mechanism used by client stubs with one supplied by client
setlocale(3c)	Modifies and queries a program's locale
setURLEntityCacheDir(3c)	Sets the directory where the DTD, schemas, and Entity files are to be cached
setURLEntityCaching(3c)	Turns caching on or off for DTD, schema, and Entity files by default
strerror(3c)	Gets error message string
strftime(3c)	Converts date and time to string
tpabort(3c)	Routine for aborting current transaction
tpacall(3c)	Routine for sending a service request
tpadmcall(3c)	Administers unbooted application
tpadvertise(3c)	Routine for advertising a service name
tpalloc(3c)	Routine for allocating typed buffers
tpbegin(3c)	Routine for beginning a transaction
tpbroadcast(3c)	Routine to broadcast notification by name

Table 1 BEA Tuxedo ATMI C Functions (Continued)

Name	Description
tpcall(3c)	Routine for sending service request and awaiting its reply
tpcancel(3c)	Routine for canceling a call descriptor for outstanding reply
tpchkauth(3c)	Routine for checking if authentication required to join an application
tpchkunsol(3c)	Routine for checking for unsolicited message
tpclose(3c)	Routine for closing a resource manager
tpcommit(3c)	Routine for committing current transaction
tpconnect(3c)	Routine for establishing a conversational service connection
tpconvert(3c)	Converts structures to/from string representations
tpconvmb(3c)	Converts encoding of characters in an input buffer to a named target encoding
tpcryptpw(3c)	Encrypts application password in administrative request
tpdequeue(3c)	Routine to dequeue a message from a queue
tpdiscon(3c)	Routine for taking down a conversational service connection
tpenqueue(3c)	Routine to enqueue a message
tpenvelope(3c)	Accesses the digital signature and encryption information associated with a typed message buffer
tperrordetail(3c)	Gets additional detail about an error generated from the last BEA Tuxedo ATMI system call
tpexport(3c)	Converts a typed message buffer into an exportable, machine-independent string representation, that includes digital signatures and encryption seals
tpforward(3c)	Routine for forwarding a service request to another service routine
tpfree(3c)	Routine for freeing a typed buffer
tpgetadmkey(3c)	Gets administrative authentication key

Table 1 BEA Tuxedo ATMI C Functions (Continued)

Name	Description
tpgetctxt(3c)	Retrieves a context identifier for the current application association
tpgetlev(3c)	Routine for checking if a transaction is in progress
tpgetmbenc(3c)	Gets the code-set encoding name from a typed buffer
tpgetrply(3c)	Routine for getting a reply from a previous request
tpgprio(3c)	Routine for getting a service request priority
tpimport(3c)	Converts an exported representation back into a typed message buffer
tpinit(3c)	Joins an application
tpkey_close(3c)	Closes a previously opened key handle
tpkey_getinfo(3c)	Gets information associated with a key handle
tpkey_open(3c)	Opens a key handle for digital signature generation, message encryption, or message decryption
tpkey_setinfo(3c)	Sets optional attribute parameters associated with a key handle
tpnotify(3c)	Routine for sending notification by client identifier
tpopen(3c)	Routine for opening a resource manager
tppost(3c)	Posts an event
tprealloc(3c)	Routine to change the size of a typed buffer
tprecv(3c)	Routine for receiving a message in a conversational connection
tpresume(3c)	Resumes a global transaction
tpreturn(3c)	Routine for returning from a service routine
tpscmt(3c)	Routine for setting when tpcommit() should return
tpseal(3c)	Marks a typed message buffer for encryption
tpsend(3c)	Routine for sending a message in a conversational connection

Table 1 BEA Tuxedo ATMI C Functions (Continued)

Name	Description
tpservice(3c)	Template for service routines
tpsetctxt(3c)	Sets a context identifier for the current application association
tpsetmbenc(3c)	Sets the code-set encoding name for a typed buffer
tpsetunsol(3c)	Sets the method for handling unsolicited messages
tpsign(3c)	Marks a typed message buffer for digital signature
tpsprio(3c)	Routine for setting service request priority
tpstrerror(3c)	Gets error message string for a BEA Tuxedo ATMI system error
tpstrerrordetail(3c)	Gets error detail message string for a BEA Tuxedo ATMI system
tpsubscribe(3c)	Subscribes to an event
tpsuspend(3c)	Suspends a global transaction
tpsvrdone(3c)	Terminates a BEA Tuxedo ATMI system server
tpsvrinit(3c)	Initializes a BEA Tuxedo ATMI system server
tpsvrthrdone(3c)	Terminates a BEA Tuxedo ATMI server thread
tpsvrthrinit(3c)	Initializes a BEA Tuxedo ATMI server thread
tpterm(3c)	Leaves an application
tptypes(3c)	Routine to determine information about a typed buffer
tpunadvertise(3c)	Routine for unadvertising a service name
tpunsubscribe(3c)	Unsubscribes to an event
TRY (3c)	Exception-returning interface
tuxgetenv(3c)	Returns value for environment name
tuxgetmbaconv(3c)	Gets the value for environment variable TPMBACONV in the process environment

Table 1 BEA Tuxedo ATMI C Functions (Continued)

Name	Description	
tuxgetmbenc(3c)	Gets the code-set encoding name for environment variable TPMBENC in the process environment	
tuxputenv(3c)	Changes or adds value to environment	
tuxreadenv(3c)	Adds variables to the environment from a file	
tuxsetmbaconv(3c)	Sets the value for environment variable TPMBACONV in the process environment	
tuxsetmbenc(3c)	Sets the code-set encoding name for environment variable TPMBENC in the process environment	
tx_begin(3c)	Begins a global transaction	
tx_close(3c)	Closes a set of resource managers	
tx_commit(3c)	Commits a global transaction	
tx_info(3c)	Returns global transaction information	
tx_open(3c)	Opens a set of resource managers	
tx_rollback(3c)	Rolls back a global transaction	
tx_set_commit_return(3c)	Sets commit_return characteristic	
tx_set_transaction_control(3c)	Sets transaction_control characteristic	
tx_set_transaction_timeout(3c)	Sets transaction_timeout characteristic	
userlog(3c)	Writes a message to the BEA Tuxedo ATMI system central event log	
Usignal(3c)	Signal handling in a BEA Tuxedo ATMI system environment	
Uunix_err(3c)	Prints UNIX system call error	

Introduction to the C Language Application-to-Transaction Monitor Interface

Description

The Application-to-Transaction Monitor Interface (ATMI) provides the interface between the application and the transaction processing system. This interface is known as the ATMI interface. It provides function calls to open and close resources, manage transactions, manage typed buffers, and invoke request/response and conversational service calls.

Communication Paradigms

The function calls described in the ATMI reference pages imply a particular model of communication. This model is expressed in terms of how client and server processes can communicate using request and reply messages.

There are two basic communication paradigms: request/response and conversational. Request/response services are invoked by service requests along with their associated data. Request/response services can receive exactly one request (upon entering the service routine) and send at most one reply (upon returning from the service routine). Conversational services, on the other hand, are invoked by connection requests along with a means of referring to the open connection (that is, a descriptor used in calling subsequent connection routines). Once the connection has been established and the service routine invoked, either the connecting program or the conversational service can send and receive data as defined by the application until the connection is torn down.

Note that a process can initiate both request/response and conversational communication, but cannot accept both request/response and conversational service requests. The following sections describe the two communication paradigms in greater detail.

Note: In various parts of the BEA Tuxedo documentation we refer to *threads*. When this term is used in a discussion of multithreaded applications, it is self-explanatory. In some instances, however, the term is used in a discussion of a topic that is relevant for both single-threaded and multithreaded applications. In such cases, readers who are running single-threaded applications may assume that the term *thread* refers to an entire process.

BEA Tuxedo ATMI System Request/ Response Paradigm for Client/Server With regard to request/response communication, a client is defined as a process that can send requests and receive replies. By definition, clients cannot receive requests nor send replies. A client can send any number of requests, and can wait for the replies synchronously or receive (some limited number of) the replies at its convenience. In certain cases, a client can send a request that has no reply. tpinit() and tpterm() allow a client to join and leave a BEA Tuxedo ATMI system application.

A request/response server is a process that can receive one (and only one) service request at a time and send at most one reply to that request. (If the server is multithreaded, however, it can receive multiple requests at one time and issue multiple replies at one time.) While a server is working on a particular request, it can act like a client by initiating request/response or conversational requests and receiving their replies. In such a capacity, a server is called a requester. Note that both client and server processes can be requesters (in fact, a client can be nothing but a requester).

A request/response server can forward a request to another request/response server. Here, the server passes along the request it received to another server and does not expect a reply. It is the responsibility of the last server in the chain to send the reply to the original requester. Use of the forwarding routine ensures that the original requester ultimately receives its reply.

Servers and service routines offer a structured approach to writing BEA Tuxedo ATMI system applications. In a server, the application writer can concentrate on the work performed by the service rather than communications details such as receiving requests and sending replies. Because many of the communication details are handled by BEA Tuxedo ATMI system's main, the application must adhere to certain conventions when writing a service routine. At the time a server finishes its service routine, it can send a reply using tpreturn() or forward the request using tpforward(). A service is not allowed to perform any other work nor is it allowed to communicate with any other process after this point. Thus, a service performed by a server is started when a request is received and ended when either a reply is sent or the request is forwarded.

Concerning request and reply messages, there is an inherent difference between the two: a request has no associated context before it is sent, but a reply does. For example, when sending a request, the caller must supply addressing information, whereas a reply is always returned to the process that originated the request, that is, addressing context is maintained for a reply and the sender of the reply can exert no control over its destination. The differences between the two message types manifest themselves in the parameters and descriptions of the routines described in tpcall().

When a request message is sent, it is sent at a particular priority. The priority affects how a request is dequeued: when a server dequeues requests, it dequeues the one with the highest priority. To prevent starvation, the oldest request is dequeued every so often regardless of priority. By default, a request's priority is associated with the service name to which the request is being sent. Service names can be given priorities at configuration time (see UBBCONFIG (5)). A default priority is used if none is defined. In addition, the priority can be set at run time using a routine, tpsprio(). By doing so, the caller can override the configuration or default priority when the message is sent.

BEA Tuxedo ATMI System Conversational Paradigm for Client/Server With regard to conversational communication, a client is defined as a process that can initiate a conversation but cannot accept a connection request.

A conversational server is a process that can receive connection requests. Once the connection has been established and the service routine invoked, either the connecting program or the conversational service can send and receive data as defined by the application until the connection is torn down. The conversation is half-duplex in nature such that one side of the connection has control and can send data until it gives up control to the other side. In a single-threaded server, while the connection is established, the server is "reserved" such that no other process can establish a connection with it. When a connection is established to a multithreaded server, however, that server is not reserved for exclusive use by one process. Instead, it can accept requests from multiple client threads.

As with a request/response server, the conversational server can act as a requester by initiating other requests or connections with other servers. Unlike a request/response server, a conversational server cannot forward a request to another server. Thus, a conversational service performed by a server is started when a request is received and ended when the final reply is sent via tpreturn().

Once the connection is established, the connection descriptor implies any context needed regarding addressing information for the participants. Messages can be sent and received as needed by the application. There is no inherent difference between the request and reply messages and no notion of priority of messages.

Message Delivery Sending and receiving messages, whether in conversation mode or request/response mode, implies communication between two units of an application. The great majority of messages lead to a reply or at least an acknowledgment, so that is an assurance that the message was received. There are, however, certain messages (some originated by the system, others originated by an application) where a reply or acknowledgment is not expected. For example, the system can send an unsolicited message using

tpnotify() without the TPACK() flag, or an application can send a message using tpacall() with the TPNOREPLY() flag. If the message queue of the receiving program is full, the message is dropped.

If the sending and receiving side are on different machines, the communication takes place between bridge processes that send and receive messages across a network. This raises the additional possibility of non-delivery due to a circuit failure. Even when either of these conditions leads to the positing of an event or to a ULOG message, it is not easy to associate the event or ULOG message with the non-arrival of a particular message.

Because the BEA Tuxedo ATMI system is designed to handle large volumes of messages across broad networks, it is not programmed to detect and correct the small percentage of failures-to-deliver described in the preceding paragraphs. For that reason, there can be no guarantee that every message will be delivered.

Message Sequencing

In the conversational model, for messages being exchanged using tpsend() and tprecv(), a sequence number is added to the message header and messages are received in the order in which they are sent. If a server or client gets a message out of order, the conversation is stopped, any transaction in progress is rolled back, and message 1572 in LIBTUX, "Bad Conversational Sequence Number," is logged.

In the Request/Response model, messages are not sequenced by the system. If the application logic implies a sequence, it is the responsibility of the application to monitor and control it. The parallel message transmission made possible by the support of multiple network addresses for bridge processes increases the possibility that messages will not be received in the order sent. An application that is concerned about this may choose to specify a single network address for each bridge process, add sequence numbers to their messages or require periodic acknowledgments.

Queued Message Model

The BEA Tuxedo ATMI system queued message model allows for enqueuing a request message to stable storage for subsequent processing without waiting for its completion, and optionally getting a reply via a queued response message. The ATMI functions that queue messages and dequeue responses are tpenqueue() and tpdequeue(). They can be called from any type of BEA Tuxedo ATMI system application processes: client, server, or conversational. The functions tpenqueue() and tpdequeue() can also be used for peer-to-peer communication where neither the enqueuing application nor the dequeuing application are designated as server or client.

The queued message facility is an XA-compliant resource manager. Persistent messages are enqueued and dequeued within transactions to ensure one-time-only processing.

ATMI Transactions

The BEA Tuxedo ATMI system supports two sets of mutually exclusive functions for defining and managing transactions: the BEA Tuxedo system's ATMI transaction demarcation functions (the names of which include the prefix tp) and X/Open's TX Interface functions (the names of which include the prefix tx). Because X/Open used ATMI's transaction demarcation functions as the base for the TX Interface, the syntax and semantics of the TX Interface are quite similar to those of the ATMI. This section is an overview of ATMI transaction concepts. The next section introduces additional concepts about the TX Interface.

In the BEA Tuxedo ATMI system, a *transaction* is used to define a single logical unit of work that either wholly succeeds or has no effect whatsoever. A transaction allows work performed in many processes, possibly at different sites, to be treated as an atomic unit of work. The initiator of a transaction normally uses tpbegin() and either tpcommit() or tpabort() to delineate the operations within a transaction.

The initiator may also suspend its work on the current transaction by issuing tpsuspend(). Another process may take over the role of the initiator of a suspended transaction by issuing tpresume(). As a transaction initiator, a process must call one of the following: tpsuspend(), tpcommit(), or tpabort(). Thus, one process can start a transaction that another may finish.

If a process calling a service is in transaction mode, then the called service routine is also placed in transaction mode on behalf of the same transaction. Otherwise, whether the service is invoked in transaction mode or not depends on options specified for the service in the configuration file. A service that is not invoked in transaction mode can define multiple transactions between the time it is invoked and the time it ends. On the other hand, a service routine invoked in transaction mode can participate in only one transaction, and work on that transaction is completed upon termination of the service routine. Note that a connection cannot be upgraded to transaction mode: if tpbegin() is called while a conversation exists, the conversation remains outside of the transaction (as if tpconnect() had been called with the TPNOTRAN() flag).

A service routine joining a transaction that was started by another process is called a *participant*. A transaction can have several participants. A service can be invoked to do work on the same transaction more than once. Only the initiator of a transaction (that is, a process calling either tpbegin() or tpresume()) can call tpcommit() or tpabort(). Participants influence the outcome of a transaction by using tpreturn() or tpforward(). These two calls signify the end of a service routine and indicate that the routine has finished its part of the transaction.

TX Transactions

Transactions defined by the TX Interface are practically identical with those defined by the ATMI functions. An application developer may use either set of functions when writing clients and service routines, but should not intermingle one set of functions with the other within a single process (that is, a process cannot call tpbegin() and later call tx commit()).

The TX Interface has two calls for opening and closing resource managers in a portable manner, $tx_open()$ and $tx_close()$, respectively. Transactions are started with $tx_begin()$ and completed with either $tx_commit()$ or $tx_rollback()$. $tx_info()$ is used to retrieve transaction information, and there are three calls to set options for transactions: $tx_set_commit_return()$,

 $tx_set_transaction_control()$, and $tx_set_transaction_timeout()$. The TX Interface has no equivalents to ATMI's tpsuspend() and tpresume().

In addition to the semantics and rules defined for ATMI transactions, the TX Interface has some additional semantics that are worth introducing here. First, service routine writers wanting to use the TX Interface must supply their own <code>tpsvrinit()</code> routine that <code>callstx_open()</code>. The default BEA Tuxedo ATMI system-supplied <code>tpsvrinit()</code> calls <code>tpopen()</code>. The same rule applies for <code>tpsvrdone()</code>: if the TX Interface is being used, then service routine writers must supply their own <code>tpsvrdone()</code> that calls <code>tx close()</code>.

Second, the TX Interface has two additional semantics not found in ATMI. These are chained and unchained transactions, and transaction characteristics.

Chained and Unchained Transactions

The TX Interface supports chained and unchained modes of transaction execution. By default, clients and service routines execute in the unchained mode; when an active transaction is completed, a new transaction does not begin until tx begin () is called.

In the chained mode, a new transaction starts implicitly when the current transaction completes. That is, when tx_commit() or tx_rollback() is called, the BEA Tuxedo ATMI system coordinates the completion of the current transaction and initiates a new transaction before returning control to the caller. (Certain failure conditions may prevent a new transaction from starting.)

Clients and service routines enable or disable the chained mode by calling $tx_set_transaction_control()$. Transitions between the chained and unchained mode affect the behavior of the next $tx_commit()$ or $tx_rollback()$ call. The call to $tx_set_transaction_control()$ does not put the caller into or take it out of transaction mode.

Since $tx_close()$ cannot be called when the caller is in transaction mode, a caller executing in chained mode must switch to unchained mode and complete the current transaction before calling $tx_close()$.

Transaction Characteristics

A client or a service routine may call tx_info() to obtain the current values of their transaction characteristics and to determine whether they are executing in transaction mode.

The state of an application process includes several transaction characteristics. The caller specifies these by calling $tx_set_*()$ functions. When a client or a service routine sets the value of a characteristic, it remains in effect until the caller specifies a different value. When the caller obtains the value of a characteristic via $tx_info()$, it does not change the value.

Error Handling

Most of the ATMI functions have one or more error returns. An error condition is indicated by an otherwise impossible returned value. This is usually -1 or error, or 0 for a bad field identifier (BADFLDID) or address. The error type is also made available in the external integer tperrno. tperrno is not cleared on successful calls, so it should be tested only after an error has been indicated.

The tpstrerror() function is provided to produce a message on the standard error output. It takes one argument, an integer (found in tperrno) and returns a pointer to the text of an error message in LIBTUX_CAT. The pointer can be used as an argument to userlog().

tperrordetail() can be used as the first step of a three step procedure to get additional detail about an error in the most recent BEA Tuxedo ATMI system call on the current thread. tperrordetail() returns an integer which is then used as an argument to tpstrerrordetail() to retrieve a pointer to a string that contains the error message. The pointer can then be used as an argument to userlog or to fprintf().

The error codes that can be produced by an ATMI function are described on each ATMI reference page. The $F_error()$ and $F_error32()$ functions are provided to produce a message on the standard error output for FML errors. They take one parameter, a string; print the argument string appended with a colon and a blank; and then print an error message followed by a newline character. The error message displayed is the one defined for the error number currently in Ferror() or Ferror32(), which is set when errors occur.

Fstrerror(), and its counterpart, Fstrerror32(), can be used to retrieve the text of an FML error message from a message catalog; it returns a pointer that can be used as an argument to userlog.

The error codes that can be produced by an FML function are described on each FML reference page.

Timeouts

There are three types of timeouts in the BEA Tuxedo ATMI system: one is associated with the duration of a transaction from start to finish. A second is associated with the maximum length of time a blocking call will remain blocked before the caller regains control. The third is a service timeout and occurs when a call exceeds the number of seconds specified in the SVCTIMEOUT parameter in the SERVICES section of the configuration file.

The first kind of timeout is specified when a transaction is started with tpbegin(). (See tpbegin(3c) for details.) The second kind of timeout can occur when using the BEA Tuxedo ATMI system communication routines defined in tpcall(3c). Callers of these routines typically block when awaiting a reply that has yet to arrive, although they can also block trying to send data (for example, if request queues are full). The maximum amount of time a caller remains blocked is determined by a BEA Tuxedo ATMI system configuration file parameter. (See the BLOCKTIME parameter in UBBCONFIG(5) for details.)

Blocking timeouts are performed by default when the caller is not in transaction mode. When a client or server is in transaction mode, it is subject to the timeout value with which the transaction was started and is not subject to the blocking timeout value specified in the <code>UBBCONFIG</code> file.

When a transaction timeout occurs, replies to asynchronous requests made in transaction mode become invalid. That is, if a process is waiting for a particular asynchronous reply for a request sent in transaction mode and a transaction timeout occurs, the descriptor for that reply becomes invalid. Similarly, if a transaction timeout occurs, an event is generated on the connection descriptor associated with the transaction and that descriptor becomes invalid. On the other hand, if a blocking timeout occurs, the descriptor is still valid and the waiting process can reissue the call to await the reply.

The service timeout mechanism provides a way for the system to kill processes that may be frozen by some unknown or unexpected system error. When a service timeout occurs in a request/response service, the BEA Tuxedo ATMI system kills the server process that is executing the frozen service and returns error code TPESVCERR. If a service timeout occurs in a conversational service, the TP EVSVCERR event is returned.

If a transaction has timed out, the only valid communications before the transaction is aborted are calls to tpacall() with TPNOREPLY, TPNOTRAN, and TPNOBLOCK set.

Since release 6.4, some additional detail has been provided beyond the TPESVCERR error code. If a service fails due to exceeding the timeout threshold, an event, .SysServiceTimeout, is posted.

Dynamic Service Advertisements

By default, a server's services are advertised when it is booted and unadvertised when it is shut down. If a server needs to control the set of services that it offers at run time, it can do so by calling <code>tpadvertise()</code> and <code>tpunadvertise()</code>. These routines affect only the services offered by the calling server unless that server belongs to a Multiple Server, Single Queue (MSSQ) set. Because all servers in an MSSQ set must offer the same set of services, these routines also affect the advertisements of all servers sharing the caller's MSSQ set.

Buffer Management

Initially, a process has no buffers. Before sending a message, a buffer must be allocated using tpalloc(). The sender's data can then be placed in the buffer and sent. This buffer has a specific structure. The particular structure is denoted by the type argument to the tpalloc() function. Since some structures can need further classification, a subtype can also be given (for example, a particular type of C structure).

When receiving a message, a buffer is required into which application data can be received. This buffer must be one originally gotten from tpalloc(). Note that a BEA Tuxedo ATMI system server, in its main, allocates a buffer whose address is passed to a request/response or conversational service upon invoking the service. (See tpservice(3c) for details on how this buffer is treated.)

Buffers used for receiving messages are treated slightly differently than those used for sending: the size and address usually change upon receipt of a message, since the system internally swaps the buffer passed into the receive call with internal buffers it used to process the buffer. A buffer may grow or shrink when it receives data. Whether it grows or shrinks depends on the amount of data sent by the sender, and the internal data flow needed to get the data from sender to receiver. Many factors can affect the buffer size, including compression, receiving a message from a different type of machine, and the action of the postrecv() function for the type of buffer being used (see buffer(3c)). The buffer sizes in Workstation clients are usually different from those in native clients.

It is best to think of the receive buffer as a placeholder, rather than the actual container that will receive the message. The system sometimes uses the size of the buffer you pass as a hint, so it does help if it is big enough to hold the expected reply.

On the sending side, buffer types that might be filled to less than their allocated capacity (for example, FML or STRING buffers) send only the amount used. A 100K FML32 buffer with one integer field in it is sent as a much smaller buffer, containing only that integer.

This means that the receiver will receive a buffer smaller than what was originally allocated by the sender, yet larger than the data that was sent. For example, if a STRING buffer of 10K bytes is allocated, and the string "HELLO" is copied into it, only the six bytes are sent, and the receiver will probably end up with a buffer that is around 1K or 4K bytes. (It may be larger or smaller, depending on other factors.) The BEA Tuxedo ATMI system guarantees only that a received message will contain all of the data that was sent; it does not guarantee that the message will contain all the free space it originally contained.

The process receiving the reply is responsible for noting size changes in the buffer (using tptypes()) and reallocating the buffer if necessary. All BEA Tuxedo ATMI functions change a receiver's buffer return information about the amount of data in the buffer, so it should become standard practice to check the buffer size every time a reply is received.

One can send and receive messages using the same data buffer. Alternatively, a different data buffer can be allocated for each message. It is usually the responsibility of the calling process to free its buffers by invoking tpfree(). However, in limited cases, the BEA Tuxedo ATMI system frees the caller's buffer. For more information about buffer usage, see the descriptions of communication functions such as tpfree().

Buffer Type Switch

The tmtype_sw_t structure provides the description required when adding new buffer types to tm_typesw(), the buffer type switch for a process. The switch elements are defined in typesw(5). The function names used in this entry are templates for the actual function names defined by the BEA Tuxedo ATMI system or by applications in which custom buffer types are created. These function names can be mapped easily to switch elements: to create a template name simply add the prefix _tm to the element name of a function pointer. For example, the template name for the element initbuf is tminitbuf.

The type element must be non-NULL and at most 8 characters in length. If this element is not unique in the switch, then subtype () must be non-NULL.

The subtype() element can be NULL, a string of at most 16 characters, or * (the wildcard character). The combination of type() and subtype() must uniquely identify an element in the switch.

A given type can have multiple subtypes. If all subtypes are to be treated the same for a given type, then the wildcard character, "*", can be used. Note that the tptypes() function can be used to determine a buffer's type and subtype if subtypes need to be distinguished. If some subset of the subtypes within a particular type are to be treated individually, and the rest are to be treated identically, then those that are to be singled out with specific subtype values should appear in the switch before the subtype designated with the wildcard. Thus, searching for types and subtypes in the switch is done from top to bottom, and the wildcard subtype entry accepts any "leftover" type matches

The dfltsize() element is used when allocating or reallocating a buffer. The semantics of tpalloc() and tprealloc() are such that the larger of the following two values is used to create or reallocate a buffer: the value of dfltsize() or the value of the size parameter for the tpalloc() and tprealloc() functions. For some types of structures, such as a fixed-sized C structure, the buffer size should equal the size of the structure. If dfltsize() is set to this value, then the caller may not need to specify the buffer's length to routines in which a buffer is passed. dfltsize() can be 0 or less. However, if tpalloc() or tprealloc() is called and the size parameter for the function being called is also less than or equal to 0, then the routine will fail. We recommend setting dfltsize() to a value greater than 0.

The BEA Tuxedo ATMI system provides five basic buffer types:

- CARRAY—a character array, possibly containing NULL characters, which is neither encoded nor decoded during transmission
- STRING—a NULL-terminated character array
- FML—fielded buffers (FML or FML32)
- XML—XML document or datagram buffer
- VIEW—simple C structures (VIEW or VIEW32); all views are handled by the same set of routines. The name of a particular view is its subtype name.

Two of these buffer types have synonyms: $x_{\texttt{OCTET}}$ is a synonym for CARRAY, and both $x_{\texttt{C}}$ TYPE and $x_{\texttt{COMMON}}$ are synonyms for VIEW. $x_{\texttt{C}}$ TYPE supports all the same elements as VIEW, whereas $x_{\texttt{COMMON}}$ supports only longs, shorts, and characters. $x_{\texttt{COMMON}}$ should be used when both C and COBOL programs are communicating.

An application wishing to supply its own buffer type can do so by adding an instance to the tm_typesw() array. Whenever adding or deleting a buffer type, be careful to leave a NULL entry at the end of the array. Note that a buffer type with a NULL name

is not permitted. An application client or server is linked with the new buffer type switch by explicitly specifying the name of the source or object file on the buildserver() or buildclient() command line using the -f option.

Unsolicited Notification

There are two methods for sending messages to application clients outside the boundaries of the client/server interaction defined above. The first is the broadcast mechanism supported by tpbroadcast(). This function allows application clients, servers, and administrators to broadcast typed buffer messages to a set of clients selected on the basis of the names assigned to them. The names assigned to clients are determined in part by the application (specifically, by the information passed in the TPINIT typed buffer at tpinit() time) and in part by the system (based on the processor through which the client accesses the application).

The second method is the notification of a particular client as identified from an earlier or current service request. Each service request contains a unique client identifier that identifies the originating client for the service request. Calls to the tpcall() and tpforward() functions from within a service routine do not change the originating client for that chain of service requests. Client identifiers can be saved and passed between application servers. The tpnotify() function is used to notify clients identified in this manner

Single or Multiple Application Contexts per Process

The BEA Tuxedo ATMI system allows client programs to create an association with one or more applications per process. If tpinit() is called with the TPMULTICONTEXTS parameter included in the flags field of the TPINIT structure, then multiple client contexts are allowed. If tpinit() is called implicitly, is called with a NULL parameter, or the flags field does not include TPMULTICONTEXTS, then only a single application association is allowed.

In single-context mode, if tpinit() is called more than once (that is, if it is called after the client has already joined the application), no action is taken and success is returned.

In multicontext mode, each call to tpinit() creates a new application association. The application can obtain a handle representing this application association by calling tpgetctxt(). Any thread in the same process can call tpsetctxt() to set that thread's context.

Once an application has chosen single-context mode, all calls to tpinit() must specify single-context mode until all application associations are terminated. Similarly, once an application has chosen multicontext mode, all calls to tpinit() must specify multicontext mode until all application associations are terminated.

Server programs can be associated with only a single application and cannot act as clients. However, within each server program, there may be multiple server dispatch contexts. Each server dispatch context works in its own thread.


Table 2 shows the transitions that may occur, within a client process, among the following states: the uninitialized state, the initialized in single-context mode state, and the initialized in multicontext mode state.

Table 2 Per-Process Context Modes

Function	States				
_	Uninitialized \mathbf{S}_0	Initialized Single-context Mode S ₁	Initialized Multicontext Mode S ₂		
tpinit without TPMULTICONTEXTS	S_1	S_1	$S_2(error)$		
tpinit with TPMULTICONTEXTS	S_2	S ₁ (error)	S_2		
Implicit tpinit	S_1	S_1	S ₂ (error)		
tpterm—not last association			S_2		
tpterm—last association		S_0	S_0		
tpterm—no association	S_0				

Context State Changes for a Client Thread In a multicontext application, calls to various functions result in context state changes for the calling thread and any other threads that are active in the same context as the calling process. The following diagram illustrates the context state changes that result from calls to the <code>tpinit()</code>, <code>tpsetctxt()</code>, and <code>tpterm()</code> functions. (The <code>tpgetctxt()</code> function does not produce any context state changes.)

Multicontext State Transitions



Note: When tpterm() is called by a thread running in the multicontext state (TPMULTICONTEXTS), the calling thread is placed in the NULL context state (TPNULLCONTEXT). All other threads associated with the terminated context are switched to the invalid context state (TPINVALIDCONTEXT).

Table 3 lists all possible context state changes produced by calling tpinit(), tpsetctxt(), and tpterm(). These states are thread-specific; different threads can be in different states when they are part of a multicontexted application. By contrast, each context state listed in the preceding table ("Per-Process Context Modes") applies to an entire process.

Table 3 Context State Changes for a Client Thread

When this	Then a thread in this context state results in					
function is executed	NULL Context	Single Context	Multicontext	Invalid Context		
tpinit without TPMULTICONTEXTS	Single context	Single context	Error	Error		
tpinit with TPMULTICONTEXTS	Multicontext	Error	Multicontext	Error		
tpsetctxt to TPNULLCONTEXT	NULL	Error	NULL	NULL		
tpsetctxt to context 0	Error	Single context	Error	Error		
tpsetctxt to context > 0	Multicontext	Error	Multicontext	Multicontext		
Implicit tpinit	Single context	N/A	N/A	Error		
tpterm in this thread	NULL	NULL	NULL	NULL		
tpterm in a different thread of this context	N/A	NULL	Invalid	N/A		

Support for Threads Programming

The BEA Tuxedo ATMI system supports multithreaded programming in several ways. If the process is using single-context mode, then as the application creates new threads, those threads share the BEA Tuxedo ATMI context for the process. In a client, after a thread issues a tpinit() call in single-context mode, other threads may then proceed to issue ATMI calls. For example, one thread may issue a tpacall() and a different thread in the same process may issue a tpgetrply().

When in multicontext mode, threads initially are not associated with a BEA Tuxedo ATMI application. A thread can either join an existing application association by calling tpsetctxt() or create a new association by calling tpinit() with the TPMULTICONTEXTS flag set.

Whether running in single-context mode or multicontext mode, the application is responsible for coordinating its threads so that ATMI operations are performed at the appropriate time.

An application may create additional threads within a server by using OS thread functions. These threads may operate independently of the BEA Tuxedo ATMI system, or they may operate in the same context as one of the server dispatch threads. Initially, application-created server threads are not associated with any server dispatch context. An application-created server thread may call tpsetctxt() to associate itself with a server dispatch thread. The application-created server thread must complete all of its ATMI calls before the dispatched thread calls tpreturn() or tpforward(). A server thread dispatched by the BEA Tuxedo ATMI system may not call tpsetctxt(). In addition, application-created threads may not make ATMI calls that would cause an implicit tpinit() when not associated with a context. On the other hand, this failure to make ATMI calls does not occur with dispatcher-created threads because those threads are always associated with a context. All server threads are prohibited from calling tpinit().

In a multithreaded application, a thread that is operating in the TPINVALIDCONTEXT state is prohibited from calling many ATMI functions. The following lists specify which functions may and may not be called under these circumstances.

The BEA Tuxedo ATMI system allows a thread operating in the TPINVALIDCONTEXT state to call the following functions:

```
■ catgets(3c)
```

- catopen, catclose(3c)
- decimal(3c)
- gp mktime(3c)
- \blacksquare nl langinfo(3c)
- rpc sm allocate, rpc ss allocate(3c)
- rpc sm client free, rpc ss client free(3c)
- rpc sm disable allocate, rpc ss disable allocate(3c)
- rpc sm enable allocate, rpc ss enable allocate(3c)
- rpc sm free, rpc ss free(3c)
- rpc sm set client alloc free, rpc ss set client alloc free(3c)
- rpc_sm_swap_client_alloc_free,
 rpc ss swap client alloc free(3c)

Introduction to the C Language Application-to-Transaction Monitor Interface

- setlocale(3c)
- strerror(3c)
- strftime(3c)
- tpalloc(3c)
- tpconvert(3c)
- tpcryptpw(3c)
- tperrordetail(3c)
- tpfree(3c)
- tpgetctxt(3c)
- tprealloc(3c)
- tpsetctxt(3c)
- tpstrerror(3c)
- tpstrerrordetail(3c)
- tpterm(3c)
- tptypes(3c)
- TRY(3c)
- tuxgetenv(3c)
- tuxputenv(3c)
- tuxreadenv(3c)
- userlog(3c)
- Usignal(3c)
- Uunix err(3c)

The BEA Tuxedo ATMI system *does not allow* a thread operating in the TPINVALIDCONTEXT state to call the following functions:

- AEWsetunsol(3c)
- tpabort(3c)
- tpacall(3c)
- tpadmcall(3c)
- tpbegin(3c)
- tpbroadcast(3c)

- tpcall(3c)
- tpcancel(3c)
- tpchkauth(3c)
- tpchkunsol(3c)
- tpclose(3c)
- tpcommit(3c)
- tpconnect(3c)
- tpdequeue(3c)
- tpenqueue(3c)
- tpgetadmkey(3c)
- tpgetlev(3c)
- tpgetrply(3c)
- tpgprio(3c)
- tpinit(3c)
- tpnotify(3c)
- tpopen(3c)
- tppost(3c)
- tprecv(3c)
- tpresume(3c)
- tpscmt(3c)
- tpsend(3c)
- tpsetunsol(3c)
- tpsprio(3c)
- tpsubscribe(3c)
- tpsuspend(3c)
- tpunsubscribe(3c)
- tx_begin(3c)
- tx close(3c)
- \blacksquare tx commit(3c)

- tx info(3c)
- tx open(3c)
- tx rollback(3c)
- tx set commit return(3c)
- tx set transaction control(3c)
- tx set transaction timeout(3c)

C Language ATMI Return Codes and Other Definitions The following return code and flag definitions are used by the ATMI routines. For an application to work with different transaction monitors without change or recompilation, each system must define its flags and return codes as follows:

```
* The following definitions must be included in atmi.h
 */
/* Flags to service routines */
 #define TPNOBLOCK
                        0x00000001 /* non-blocking send/rcv */
#define RESERVED BIT1 0x00000200 /* reserved for future use */
 #define TPCONV 0x00000400 /* conversational service */
 #define TPSENDONLY 0x00000800 /* send-only mode */
#define TPRECVONLY 0x00001000 /* recv-only mode */
#define TPACK 0x00002000 /* */
/* Flags to tpreturn - also defined in xa.h */
 #define TPFAIL 0x20000000 /* service FAILURE for tpreturn */
#define TPEXIT 0x08000000 /* service FAILURE with server exit */
#define TPSUCCESS 0x04000000 /* service SUCCESS for tpreturn */
/* Flags to tpscmt - Valid TP COMMIT CONTROL
 * characteristic values
 */
 #define TP CMT LOGGED 0x01 /* return after commit
```

```
* decision is logged */
 #define TP CMT COMPLETE 0x02
                                 /* return after commit has
                                  * completed */
/* client identifier structure */
struct clientid t {
                           /* reserved for internal use */
long clientdata[4];
typedef struct clientid t CLIENTID;
/* context identifier structure */
typedef long TPCONTEXT T;
/* interface to service routines */
struct tpsvcinfo {
name[32];
long flags;
                                /* describes service attributes */
char *data;
                                /* pointer to data */
long len;
                                /* request data length */
int cd;
                                /* connection descriptor
* if (flags TPCONV) true */
                                /* application authentication client
long appkey;
* key */
CLIENTID cltid;
                               /* client identifier for originating
 * client */
};
typedef struct tpsvcinfo TPSVCINFO;
/* tpinit(3c) interface structure */
 #define MAXTIDENT
                                 30
struct tpinfo t {
char usrname[MAXTIDENT+2];
                             /* client user name */
char cltname[MAXTIDENT+2];
                                /* app client name */
char passwd[MAXTIDENT+2];
                                /* application password */
long flags;
                                /* initialization flags */
long datalen;
                                /* length of app specific data */
                                /* placeholder for app data */
long data;
typedef struct tpinfo t TPINIT;
/* The transactionID structure passed to tpsuspend(3c) and tpresume(3c) */
struct tp tranid t {
long info[6];
                                /* Internally defined */
};
typedef struct tp tranid t TPTRANID;
```

```
/* Flags for TPINIT */
                                    0x00000007 /* unsolicited notification
 #define TPU MASK
                                                      * mask */
                                    0x00000001 /* signal based
 #define TPU SIG
                                     * notification */
                                    0x00000002 /* dip-in based
 #define TPU DIP
                                     * notification */
 #define TPU IGN
                                    0x00000004 /* ignore unsolicited
                                    #define TPU THREAD
#define TPSA_FASTPATH
                                                      * fastpath */
 #define TPSA PROTECTED
                                   0x0000010
                                                      /* System access ==
                                                      * protected */
 #define TPMULTICONTEXTS
                                    0x00000020
                                                      /* multiple context associa-
                                                      * tions per process */
 /* /Q tpgctl t data structure
 #define TMONAMELEN
                                     15
 #define TMMSGIDLEN
                                     32
 #define TMCORRIDLEN
                                     32
                                   /* control parameters to queue primitives */
struct tpqctl t {
long flags; /* indicates which values are set */
long deq_time; /* absolute/relative time for dequeuing */
long priority; /* enqueue priority */
long diagnostic; /* indicates reason for failure */
char msgid[TMMSGIDLEN]; /* ID of message before which to queue */
char corrid[TMCORRIDLEN]; /* correlation ID used to identify message */
char replyqueue[TMQNAMELEN+1]; /* queue name for reply message */
 char failurequeue[TMQNAMELEN+1]; /* queue name for failure message */
CLIENTID cltid;
                                    /* client identifier for */
                                    /* originating client */
                                    /* application user-return code */
long urcode;
                                   /* application authentication client key */
long appkey;
long delivery_qos;
                                    /* delivery quality of service */
long reply gos;
                                   /* reply message quality of service */
long exp time
                                    /* expiration time */
};
 typedef struct tpqctl t TPQCTL;
/* /Q structure elements that are valid - set in flags */
 #ifndef TPNOFLAGS
                             0x00000 /* no flags set -- no get */
 #define TPNOFLAGS
 #endif
 #define TPOCORRID
                                   0x00001 /* set/get correlation ID */
 #define TPQFAILUREQ
                                   0x00002 /* set/get failure queue */
0x00004 /* enqueue before message ID */
 #define TPQBEFOREMSGID
 #define TPQGETBYMSGIDOLD
                                    0x00008 /* deprecated */
 #define TPOMSGID
                                    0x00010 /* get msgid of eng/deg message */
```

```
#define TPQPRIORITY
                                       0x00020
                                                  /* set/get message priority */
                                      0x00040 /* enqueue at queue top */
 #define TPQTOP
#define TPOPEEK
                                      0x01000 /* non-destructive dequeue */
#define TPQPEEK 0x01000 /* Holl-destructive dequede /
#define TPQDELIVERYQOS 0x02000 /* delivery quality of service */
#define TPQREPLYQOS 0x04000 /* reply msg quality of service*/
#define TPQEXPTIME_ABS 0x08000 /* absolute expiration time */
#define TPQEXPTIME_REL 0x10000 /* relative expiration time */
#define TPQEXPTIME_NONE 0x20000 /* never expire */
#define TPQGETBYMSGID 0x40008 /* dequeue by msgid */
 #define TPQGETBYCORRID 0x80800 /* dequeue by corrid */
/* Valid flags for the quality of service fields in the TPQCTL structure */
 #define TPQQOSDEFAULTPERSIST 0x00001 /* queue's default persistence */
                                                   /* policy */
 #define TPQQOSPERSISTENT 0x00002 /* disk message */
 #define TPOOOSNONPERSISTENT
                                      0x00004 /* memory message */
/* error return codes */
 extern int tperrno;
 extern long tpurcode;
/* tperrno values - error codes */
 * The reference pages explain the context in which the following
 * error codes can return.
 * /
 #define TPMINVAL
                                      0
                                                   /* minimum error message */
 #define TPEABORT
                                       1
 #define TPEBADDESC
                                       2
 #define TPEBLOCK
                                       3
                                       4
 #define TPEINVAL
 #define TPELIMIT
                                       5
 #define TPENOENT
                                       7
 #define TPEOS
                                       8
 #define TPEPERM
 #define TPEPROTO
                                       9
 #define TPESVCERR
                                       10
                                       11
 #define TPESVCFAIL
 #define TPESYSTEM
                                       12
 #define TPETIME
                                       1.3
 #define TPETRAN
                                       14
 #define TPGOTSIG
                                       1.5
 #define TPERMERR
                                       16
 #define TPEITYPE
                                       17
```

```
#define TPEOTYPE
                                 18
 #define TPERELEASE
                                 19
 #define TPEHAZARD
                                20
 #define TPEHEURISTIC
                                21
 #define TPEEVENT
                                22
 #define TPEMATCH
                                2.3
 #define TPEDIAGNOSTIC
                                24
 #define TPEMIB
                                25
                                           /* maximum error message */
 #define TPMAXVAL
                                26
/* conversations - events */
#define TPEV_DISCONIMM
#define TPEV_SVCERR
#define TPEV_SVCFAIL
                               0×0001
                                0x0002
#define TPEV_SVCFAIL 0x0004
#define TPEV_SVCSUCC 0x0008
#define TPEV_SENDONLY 0x0020
/* /Q diagnostic codes
 #define OMEINVAL
                                -1
 #define QMEBADRMID
                                -2
                                -3
 #define OMENOTOPEN
 #define OMETRAN
                                -4
 #define QMEBADMSGID
                                -5
#define QMESYSTEM
                                -6
                                -7
 #define QMEOS
 #define QMEABORTED
                                -8
                               QMEABORTED
 #define QMENOTA
 #define QMEPROTO
#define QMEBADQUEUE
                                -10
 #define OMENOMSG
                                -11
                               -12
 #define OMEINUSE
 #define QMENOSPACE
                               -13
#define QMERELEASE
                               -14
-15
 #define OMEINVHANDLE
 #define QMESHARE
                                -16
/* EventBroker Messages */
                               0x0000001
 #define TPEVSERVICE
 #define TPEVQUEUE
                                0×00000002
 #define TPEVTRAN
                                0x00000004
#define TPEVPERSIST
                                0x00000008
/* Subscription Control Structure */
 struct tpevctl t {
    long flags;
    char name1 [XATMI SERVICE NAME LENGTH];
    char name2[XATMI SERVICE NAME LENGTH];
    TPQCTL qctl;
```

```
};
typedef struct tpevctl t TPEVCTL;
```

C Language TX
Return Codes
and Other
Definitions

The following return code and flag definitions are used by the TX routines. For an application to work with different transaction monitors without change or recompilation, each system must define its flags and return codes as follows:

```
/* current version of this
#define TX H VERSION
                                          * header file */
/*
 * Transaction identifier
                       128
                                         /* size in bytes */
 #define XIDDATASIZE
 struct xid t {
        long formatID;
                                         /* format identifier */
        long gtrid length;
                                         /* value not to exceed 64 */
                                         /* value not to exceed 64 */
        long bqual length;
        char data[XIDDATASIZE];
 typedef struct xid t XID;
 * A value of -1 in formatID means that the XID is null.
 * Definitions for tx routines
 /* commit return values */
 typedef long COMMIT RETURN;
  #define TX COMMIT COMPLETED 0
 #define TX COMMIT DECISION LOGGED 1
/* transaction control values */
 typedef long TRANSACTION CONTROL;
 #define TX UNCHAINED 0
 #define TX CHAINED 1
/* type of transaction timeouts */
 typedef long TRANSACTION TIMEOUT;
/* transaction state values */
 typedef long TRANSACTION STATE;
 #define TX ACTIVE 0
 #define TX TIMEOUT ROLLBACK ONLY 1
 #define TX ROLLBACK ONLY 2
```

```
/* structure populated by tx info */
struct tx info t {
       XID xid;
       COMMIT RETURN when return;
       TRANSACTION CONTROL transaction control;
       TRANSACTION TIMEOUT transaction timeout;
       TRANSACTION STATE transaction state;
typedef struct tx info t TXINFO;
/*
* tx return codes
* (transaction manager reports to application)
#define TX NOT SUPPORTED
                           1 /* option not supported */
#define TX OK
                                  0 /* normal execution */
#define TX OUTSIDE
                                  -1 /* application is in an RM
                                     * local transaction */
#define TX ROLLBACK
                                   -2 /* transaction was rolled
                                     * back */
                                   -3 /* transaction was
#define TX MIXED
                                      * partially committed and
                                      * partially rolled back */
                                   -4 /* transaction may have been
#define TX HAZARD
                                      * partially committed and
                                      * partially rolled back */
                                   -5 /* routine invoked in an
#define TX PROTOCOL ERROR
                                     * improper context */
#define TX ERROR
                                   -6 /* transient error */
#define TX FAIL
                                  -7 /* fatal error */
#define TX EINVAL
                                 -8 /* invalid arguments were given */
#define TX COMMITTED
                                 -9 /* transaction has
                                      * heuristically committed */
                                   -100 /* transaction committed plus
#define TX NO BEGIN
                                        * new transaction could not
                                         * be started */
                                   (TX ROLLBACK+TX NO BEGIN)
#define TX ROLLBACK NO BEGIN
                                       /* transaction rollback plus
                                        * new transaction could not
                                        * be started */
#define TX MIXED NO BEGIN
                                   (TX MIXED+TX NO BEGIN)
                                       /* mixed plus new transaction
                                        * could not be started */
                                  (TX HAZARD+TX NO BEGIN)
#define TX HAZARD NO BEGIN
                                        /* hazard plus new transaction
                                        * could not be started */
#define TX COMMITTED NO BEGIN (TX COMMITTED+TX NO BEGIN)
```

- /* heuristically committed plus
 - * new transaction could not
 - * be started */

ATMI State Transitions

The BEA Tuxedo ATMI system keeps track of the state for each process and verifies that legal state transitions occur for the various function calls and options. The state information includes the process type (request/response server, conversational server, or client), the initialization state (uninitialized or initialized), the resource management state (closed or open), the transaction state of the process, and the state of all asynchronous request and connection descriptors. When an illegal state transition is attempted, the called function fails, setting tperroo to TPEPROTO. The legal states and transitions for this information are described in the following tables.

Table 4 indicates which functions may be called by request/response servers, conversational servers, and clients. Note that tpsvrinit(), tpsvrdone(), tpsvrthrinit(), and tpsvrthrdone() are not included in this table because they are not called by applications (that is, they are application-supplied functions that are invoked by the BEA Tuxedo ATMI system).

Table 4 Available Functions

Function	Pı	Process Type		
	Request/Response Server	Conversational Server	Client	
tpabort	Y	Y	Y	
tpacall	Y	Y	Y	
tpadvertise	Y	Y	N	
tpalloc	Y	Y	Y	
tpbegin	Y	Y	Y	
tpbroadcast	Y	Y	Y	
tpcall	Y	Y	Y	
tpcancel	Y	Y	Y	
tpchkauth	Y	Y	Y	
tpchkunsol	N	N	Y	

Table 4 Available Functions (Continued)

Function	Pı	cocess Type	
	Request/Response Server	Conversational Server	Client
tpclose	Y	Y	Y
tpcommit	Y	Y	Y
tpconnect	Y	Y	Y
tpdequeue	Y	Y	Y
tpdiscon	Y	Y	Y
tpenqueue	Y	Y	Y
tpforward	Y	N	N
tpfree	Y	Y	Y
tpgetctxt	Y	Y	Y
tpgetlev	Y	Y	Y
tpgetrply	Y	Y	Y
tpgprio	Y	Y	Y
tpinit	N	N	Y
tpnotify	Y	Y	Y
tpopen	Y	Y	Y
tppost	Y	Y	Y
tprealloc	Y	Y	Y
tprecv	Y	Y	Y
tpresume	Y	Y	Y
tpreturn	Y	Y	N
tpscmt	Y	Y	Y

Table 4 Available Functions (Continued)

Function	I	Process Type	
	Request/Response Server	Conversational Server	Client
tpsend	Y	Y	Y
tpservice	Y	Y	N
tpsetctxt	Y (in application- created threads)	Y (in application- created threads)	Y
tpsetunsol	N	N	Y
tpsprio	Y	Y	Y
tpsubscribe	Y	Y	Y
tpsuspend	Y	Y	Y
tpterm	N	N	Y
tptypes	Y	Y	Y
tpunadvertise	Y	Y	
tpunsubscribe	Y	Y	Y

The remaining state tables are for both clients and servers, unless otherwise noted. Keep in mind that because some functions cannot be called by both clients and servers (for example, tpinit()), certain state transitions shown below may not be possible for both process types. The above table should be consulted to determine whether the process in question is allowed to call a particular function.

The following state table indicates whether or not a thread in a client process has been initialized and registered with the transaction manager. Note that this table assumes the use of tpinit(), which is optional in single-context mode. That is, a single-context client may implicitly join an application by issuing one of many ATMI functions (for example, tpconnect() or tpcall()). A client must use tpinit() when one of the following is true:

 Application authentication is required. (See tpinit (3c) and the description of the SECURITY keyword in UBBCONFIG (5) for details.)

- The client wants to access an XA-compliant resource manager directly. (See tpinit(3c) for details.)
- The client wants to create multiple application associations.

A server is placed in the initialized state by the BEA Tuxedo ATMI system's main() before its tpsvrinit() function is invoked, and it is placed in the uninitialized state by the BEA Tuxedo ATMI system's main() after its tpsvrdone() function has returned. Note that in all of the state tables shown below, an error return from a function causes the thread to remain in the same state, unless otherwise noted.

Table 5 Thread Initialization States

Function	Stat	tes
	Uninitialize I ₀	Initialize I ₁
tpalloc	I_0	I_1
tpchkauth	I_0	I ₁
tpfree	I_0	I ₁
tpgetctxt	I_0	I ₁
tpinit	I_1	I ₁
tprealloc	I_0	I ₁
tpsetctxt (set to a non-NULL context)	I ₁	I ₁
tpsetctxt (with the TPNULLCONTEXT context set)	I_0	I_0
tpsetunsol	I_0	I ₁
tpterm (in this thread)	I_0	I_0
tpterm (in a different thread of this context)	I_0	I_0

Table 5 Thread Initialization States (Continued)

Function	States			
	Uninitialize I ₀	Initialize I ₁		
tptypes	I_0	I_1		
All other ATMI functions	I ₁	I ₁		

The remaining state tables assume a precondition of state I_1 (regardless of whether a process arrived in this state via tpinit(), tpsetctxt(), or the BEA Tuxedo ATMI system's main()).

Table 6 indicates the state of a client or server with respect to whether or not a resource manager associated with the process has been initialized.

Table 6 Resource Management States

Function	Sta	tes
-	Closed R ₀	Open R ₁
tpopen	R_1	R_1
tpclose	R_0	R_0
tpbegin		R_1
tpcommit		R ₁
tpabort		R ₁
tpsuspend		R ₁
tpresume		R ₁
tpservice with flag TPTRAN		R_1
All other ATMI functions	R_0	R ₁

Table 7 indicates the state of a process with respect to whether or not the process is associated with a transaction. For servers, transitions to states T_1 and T_2 assume a precondition of state R_1 (for example, tpopen() has been called with no subsequent call to tpclose() or tpterm()).

Table 7 Transaction State of Application Association

Function			
	Not in Transaction T ₀	Initiator T ₁	Participant T ₂
tpbegin			
tpabort		T_0	
tpcommit		T_0	
tpsuspend		T_0	
tpresume	T ₁	T_0	
tpservice with flag TPTRAN	T ₂		
tpservice (not in transaction mode)	T ₀		
tpreturn	T_0		T_0
tpforward	T_0		T_0
tpclose	R_0		
tpterm	I_0	T_0	
All other ATMI functions	T_0	T_1	T ₂

Table 8 indicates the state of a single request descriptor returned by tpacall().

Table 8 Asynchronous Request Descriptor States

Function	Sta	ntes
	No Descriptor A ₀	Valid Descriptor A ₁
tpacall	A_1	
tpgetrply		A_0
tpcancel		$A_0^{\ a}$
tpabort	A_0	$A_0^{\ b}$
tpcommit	A_0	$A_0^{\ b}$
tpsuspend	A_0	A ₁ ^c
tpreturn	A_0	A_0
tpforward	A_0	A_0
tpterm	I_0	I_0
All other ATMI functions	A_0	A_1

Note: ^a This state change occurs only if the descriptor is not associated with the caller's transaction.

Table 9 indicates the state of a connection descriptor returned by tpconnect() or provided by a service invocation in the TPSVCINFO structure. For primitives that do not take a connection descriptor, the state changes apply to all connection descriptors, unless otherwise noted.

^b This state change occurs only if the descriptor is associated with the caller's transaction.

^c If the descriptor is associated with the caller's transaction, then tpsuspend() returns a protocol error.

The states are as follows:

- C₀—No descriptor
- lacktriangledown C_1 —tpconnect() descriptor send-only
- \blacksquare C₂—tpconnect() descriptor receive-only
- C₃—TPSVCINFO descriptor send-only
- lacktriangledown C_4 —TPSVCINFO descriptor receive-only

Table 9 Connection Request Descriptor States

Function/Event	States				
	C_0	C_1	C_2	C_3	C ₄
tpconnect with TPSENDONLY	$C_1^{\ a}$				
tpconnect with TPRECVONLY	C ₂ ^a				
tpservice with flag TPSENDONLY	C ₃ ^b				
tpservice with flag TPRECVONLY	C ₄ ^b				
tprecv/no event			C ₂		C ₄
tprecv/TPEV_SENDONLY			C_1		C ₃
tprecv/TPEV_DISCONIMM			C_0		C_0
tprecv/TPEV_SVCERR			C_0		
tprecv/TPEV_SVCFAIL			C_0		
tprecv/TPEV_SVCSUCC			C_0		
tpsend/no event		C ₁		C_3	
tpsend with flag TPRECVONLY		C ₂		C_4	
tpsend/TPEV_DISCONIMM		C_0		C_0	

Table 9 Connection Request Descriptor States (Continued)

Function/Event	States				
	C_0	C ₁	C_2	C ₃	C_4
tpsend/TPEV_SVCERR		C_0			
tpsend/TPEV_SVCFAIL		C_0			
tpterm (client only)	C_0	C_0			
tpcommit (originator only)	C_0	C_0 c	C_0^c		
tpsuspend (originator only)	C_0	C_1^{d}	C_2^{d}		
tpabort (originator only)	C_0	$C_0^{\ c}$	C ₀ c		
tpdiscon		C_0	C_0		
tpreturn (CONV server)		C_0	C_0	C_0	C_0
tpforward (CONV server)		C_0	C_0	C_0	C_0
All other ATMI functions	C_0	C_1	C ₂	C ₃	C ₄

Note: ^a If process is in transaction mode and TPNOTRAN is not specified, the connection is in transaction mode.

TX State Transitions

The BEA Tuxedo ATMI system ensures that a process calls the TX functions in a legal sequence. When an illegal state transition is attempted (that is, a call from a state with a blank transition entry), the called function returns <code>TX_PROTOCOL_ERROR</code>. The legal states and transitions for the TX functions are shown in Table 10. Calls that return failure do not make state transitions, unless they are described by specific state table entries. Any BEA Tuxedo ATMI system client or server is allowed to use the TX functions.

^b If the TPTRAN flag is set, the connection is in transaction mode.

^c If the connection is not in transaction mode, no state change.

^d If the connection is in transaction mode, then tpsuspend() returns a protocol error.

The states are defined below:

- S_0 : No RMs have been opened or initialized. An application association cannot start a global transaction until it has successfully called tx_open.
- S₁: An application association has opened its RM but is not in a transaction. Its transaction control characteristic is TX UNCHAINED.
- S₂: An application association has opened its RM but is not in a transaction. Its transaction control characteristic is TX CHAINED.
- S₃: An application association has opened its RM and is in a transaction. Its transaction control characteristic is TX UNCHAINED.
- lacksquare S₄: An application association has opened its RM and is in a transaction. Its transaction control characteristic is TX CHAINED.

Table 10 TX Function States and Transitions

Function			States		
	S_0	S_1	S_2	S_3	S_4
tx_begin		S_3	S_4		
tx_close	S ₀	S_0	S_0		
tx_commit -> TX_SET1				S_1	S ₄
tx_commit -> TX_SET2					S ₂
tx_info		S_1	S_2	S_3	S ₄
tx_open	S_1	S_1	S_2	S_3	S ₄
tx_rollback -> TX_SET1				S_1	S ₄
tx_rollback -> TX_SET2					S_2
tx_set_commit_return		S ₁	S ₂	S ₃	S ₄
<pre>tx_set_transaction_control control = TX_CHAINED</pre>		S_2	S_2	S_4	S_4

Table 10 TX Function States and Transitions (Continued)

Function			States		
	S_0	S_1	S_2	S_3	S_4
<pre>tx_set_transaction_control control = TX_UNCHAINED</pre>		S_1	S_1	S_3	S_3
tx_set_transaction_timeout		S_1	S_2	S_3	S_4

- TX_SET1 denotes any of the following: TX_OK, TX_ROLLBACK, TX_MIXED, TX_HAZARD, or TX_COMMITTED. TX_ROLLBACK is not returned by tx rollback() and TX COMMITTED is not returned by tx commit().
- TX_SET2 denotes any of the following: TX_NO_BEGIN,

 TX_ROLLBACK_NO_BEGIN, TX_MIXED_NO_BEGIN, TX_HAZARD_NO_BEGIN, or

 TX_COMMITTED_NO_BEGIN. TX_ROLLBACK_NO_BEGIN is not returned by

 tx_rollback() and TX_COMMITTED_NO_BEGIN is not returned by

 tx_commit().
- If TX_FAIL is returned on any call, the application process is in an undefined state with respect to the above table.
- When tx_info() returns either TX_ROLLBACK_ONLY or TX_TIMEOUT_ROLLBACK_ONLY in the transaction state information, the transaction is marked rollback-only and will be rolled back whether the application program calls tx_commit() or tx_rollback().

See Also

buffer(3c), tpadvertise(3c), tpalloc(3c), tpbegin(3c), tpcall(3c),
tpconnect(3c), tpgetctxt(3c), tpinit(3c), tpopen(3c), tpservice(3c),
tpsetctxt(3c), tuxtypes(5), typesw(5)

AEMsetblockinghook(3c)

Name

AEMsetblockinghook()—Establishes an application-specific blocking hook function.

Synopsis

```
#include <atmi.h>
int AEMsetblockinghook( TM FARPROC)
```

Description

AEMsetblockinghook() is an "ATMI Extension for Mac" that allows a Mac task to install a new function which the ATMI networking software uses to implement blocking ATMI calls. It takes a pointer to the procedure instance address of the blocking function to be installed.

A default function, by which blocking ATMI calls are handled, is included. The function AEMsetblockinghook() gives the application the ability to execute its own function at "blocking" time in place of the default function. If called with a NULL pointer, the blocking hook function is reset to the default function.

When an application invokes a blocking ATMI operation, the operation is initiated and then a loop is entered which is equivalent to the following pseudocode:

```
for(;;) {
    execute operation in non-blocking mode
    if error
        break;
    if operation complete
        break;
    while(BlockingHook())
    ;
}
```

Return Values

AEMsetblockinghook() returns a pointer to the procedure-instance of the previously installed blocking function. The application or library that calls the AEMsetblockinghook() function should save this return value so that it can be restored if necessary. (If "nesting" is not important, the application may simply discard the value returned by AEMsetblockinghook() and eventually use AEMsetblockinghook() to restore the default mechanism.)
AEMsetblockinghook() returns NULL on error and sets tperrno to indicate the error condition.

Errors

Under failure, AEMsetblockinghook() sets tperrno to the following value:

```
[TPEPROTO]
```

AEMsetblockinghook() was called while a blocking operation was in progress.

Section 3c - C Functions

Portability This interface is supported only in Mac clients.

Notices The blocking function is reset after tpterm(3c) is called by the application.

AEOaddtypesw(3c)

Name AEOaddtypesw()—Installs or replaces a user-defined buffer type at execution time.

Synopsis #include <atmi.h>
#include <tmtypes.h>

int FAR PASCAL AEOaddtypesw(TMTYPESW *newtype)

Description

AEOaddtypesw() is an "ATMI Extension for OS/2" that allows an OS/2 client to install a new, or replace an existing, user-defined buffer type at execution time. The argument to this function is a pointer to a TMTYPESW structure that contains the information for the buffer type to be installed.

If the type () and the subtype () match an existing buffer type already installed, then all the information is replaced with the new buffer type. If the information does not match the type () and the subtype () fields, then the new buffer type is added to the existing types registered with the BEA Tuxedo ATMI system. For new buffer types, make sure that the WSH and other BEA Tuxedo ATMI system processes involved in the call processing have been built with the new buffer type.

The function pointers in the TMTYPESW array should appear in the Module Definition file of the application in the EXPORTS section.

The application can also use the BEA Tuxedo ATMI system's defined buffer type routines. The application and the BEA Tuxedo ATMI system's buffer routines can be intermixed in one user defined buffer type.

Return Values

Upon success, AEOaddtypesw() returns the number of user buffer types in the system Upon failure, AEOaddtypesw() returns -1 and sets tperrno to indicate the error condition.

Errors

Upon failure, AEOaddtypesw() sets tperrno to one of the following values:

[TPEINVAL]

AEOaddtypesw() was called and the type parameter was NULL.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

Portability

This interface is supported only in Windows clients. The preferred way to install a type switch is to add it to the BEA Tuxedo ATMI system type switch DLL. Please refer to *Setting Up a BEA Tuxedo Application* for more information.

Notices FAR PASCAL is used only for the 16-bit OS/2 environment.

Examples

```
#include <os2.h>
#include <atmi.h>
#include <tmtypes.h>
int FAR PASCAL Nfinit (char FAR *, long);
int (FAR PASCAL * lpFinit) (char FAR *, long);
int FAR PASCAL Nfreinit(char FAR *, long);
int (FAR PASCAL * lpFreinit) (char FAR *, long);
int FAR PASCAL Nfuninit(char FAR *, long);
int (FAR PASCAL * lpFuninit) (char FAR *, long);
TMTYPESW newtype =
                "",
"MYFML",
                                1024,
                                                NULL,
                                                                NULL,
               fpresend, fpostsend, fpostrecv, fencdec,
NULL,
froute
};
  newtype.initbuf = Nfinit;
   newtype.reinitbuf = Nfreinit;
  newtype.uninitbuf = Nfuninit;
   if (AEOaddtypesw(newtype) == -1) {
          userlog("AEOaddtypesw failed %s", tpstrerror(tperrno));
   }
int.
FAR PASCAL
Nfinit (char FAR *ptr, long len)
     . . . . . .
    return(1);
}
int
FAR PASCAL
Nfreinit(char FAR *ptr, long len)
{
     . . . . . .
    return(1);
}
int.
FAR PASCAL
Nfuninit(char FAR *ptr, long mdlen)
{
```

AEPisblocked(3c)

Name AEPisblocked()—Determines if a blocking call is in progress.

Synopsis #include <atmi.h>

int far pascal AEPisblocked(void)

Description AEPisblocked() is an "ATMI Extension for OS/2 Presentation Manager" that allows

a OS/2 PM task to determine if it is executing while waiting for a previous blocking

call to complete.

Return Values If there is an outstanding blocking function awaiting completion, AEPisblocked()

returns 1. Otherwise, it returns 0.

Errors No errors are returned.

Portability This interface is supported only in OS/2 PM clients.

Comments Although a blocking ATMI call appears to an application as though it "blocks," the

OS/2 PM ATMI DLL has to relinquish the processor to allow other applications to run. This means that it is possible for the application which issued the blocking call to be

reentered, depending on the message(s) it receives. In this instance, the

AEPisblocked() function can be used to ascertain whether the task has been

reentered while waiting for an outstanding blocking call to complete. Note that ATMI

prohibits more than one outstanding call per thread.

See Also AEMsetblockinghook(3c)

AEWsetunsol(3c)

Name AEWsetunsol()—Posts a Windows message for BEA Tuxedo ATMI unsolicited

event.

Synopsis #include <windows.h>

#include <atmi.h>

int far pascal AEWsetunsol(HWND hWnd, WORD wMsg)

Description In certain Microsoft Windows programming environments, it is natural and convenient

for the BEA Tuxedo ATMI system's unsolicited messages to be posted to the

Windows event message queue.

AEWsetunsol() controls which window to notify, hWnd, and which Windows message type to post, wMsg. When a BEA Tuxedo ATMI unsolicited message arrives, a Windows message is posted. lParam() is set to the BEA Tuxedo ATMI system buffer pointer, or zero if none. If lParam() is non-zero, the application must call

tpfree() to release the buffer.

If wMsg is zero, any future unsolicited messages will be logged and ignored.

In a multithreaded application, a thread in the $\mathtt{TPINVALIDCONTEXT}$ state is not allowed

to issue a call to AEWsetunsol().

Return Values Upon failure, AEWsetunsol () returns -1 and sets tperrno to indicate the error

condition.

Errors Upon failure, AEWsetunsol () sets tperrno to one of the following values:

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

Portability This interface is supported only in Microsoft Windows clients.

Notices AEWsetunsol() posting of Windows messages may not be activated simultaneously

with a tpsetunsol() callback routine. The most recent tpsetunsol() or AEWsetunsol() request controls how unsolicited messages will be handled.

See Also tpsetunsol(3c)

buffer(3c)

Name buffer()—Semantics of elements in tmtype sw t.

Synopsis

```
int
        /* Initialize a new data buffer */
tminitbuf(char *ptr, long len)
int /* Reinitialize a reallocated data buffer */
tmreinitbuf(char *ptr, long len)
int /* Uninitialize a data buffer to be freed */
tmuninitbuf(char *ptr, long len)
long
     /* Process buffer before sending */
tmpresend(char *ptr, long dlen, long mdlen)
void /* Process buffer after sending */
tmpostsend(char *ptr, long dlen, long mdlen)
long /* Process buffer after receiving */
tmpostrecv(char *ptr, long dlen, long mdlen)
long /* Encode/decode a buffer to/from a transmission format */
 tmencdec(int op, char *encobj, long elen, char *obj, long olen)
int /* Determine server group for routing based on data */
 tmroute(char *routing name, char *service, char *data, long \ len, char *group)
int /* Evaluate boolean expression on buffer's data */
 tmfilter(char *ptr, long dlen, char *expr, long exprlen)
int /* Extract buffer's data based on format string */
 tmformat(char *ptr, long dlen, char *fmt, char *result, long \ maxresult)
long /* Process buffer before sending, possibly generating copy */
 tmpresend2(char *iptr, long ilen, long mdlen, char *optr, long olen, long *flags)
long /* Multibyte code-set encoding conversion */
tmconvmb(char *ibufp, long ilen, char *enc name, char *obufp, long olen, long
    *flags)
```

Description

This page describes the semantics of the elements and routines defined in the tmtype_sw_t structure. These descriptions are necessary for adding new buffer types to a process buffer type switch, tm_typesw. The switch elements are defined in typesw(5). The function names used in this entry are templates for the actual function names defined by the BEA Tuxedo ATMI system as well as by applications adding their own buffer types. The names map to the switch elements very simply: the template names are made by taking each function pointer's element name and prepending _tm (for example, the element initbuf has the function name tminitbuf()).

The element type must be non-NULL and up to 8 characters in length. The element subtype can be NULL, a string of up to 16 characters, or the wildcard character, "*". If type is not unique in the switch, then subtype must be used; the combination of type and subtype must uniquely identify an element in the switch.

A given type can have multiple subtypes. If all subtypes are to be treated the same for a given type, then the wildcard character, "*", can be used. Note that the function tptypes() can be used to determine a buffer's type and subtype if subtypes need to be distinguished. If some subset of the subtypes within a particular type are to be treated individually, and the rest are to be treated identically, then those which are to be singled out with specific subtype values should appear in the switch before the subtype designated with the wildcard. Thus, searching for types and subtypes in the switch is done from top to bottom, and the wildcard subtype entry accepts any "leftover" type matches.

dfltsize() is used when allocating or reallocating a buffer. The larger of dfltsize() and the routines' size parameter is used to create or reallocate a buffer. For some types of structures, like a fixed sized C structure, the buffer size should equal the size of the structure. If dfltsize() is set to this value, then the caller may not need to specify the buffer's length to routines in which a buffer is passed. dfltsize() can be 0 or less; however, if tpalloc() or tprealloc() is called and its size parameter is also less than or equal to 0, then the routine will fail. It is not recommended to set dfltsize() to a value less than 0.

Routine Specifics

The names of the functions specified below are template names used within the BEA Tuxedo ATMI system. Any application adding new routines to the buffer type switch must use names that correspond to real functions, either provided by the application or library routines. If a NULL function pointer is stored in a buffer type switch entry, the BEA Tuxedo ATMI system calls a default function that takes the correct number and type of arguments, and returns a default value.

tminitbuf

_tminitbuf() is called from within tpalloc() after a buffer has been allocated. It is passed a pointer to the new buffer, ptr, along with its size so that the buffer can be initialized appropriately. len is the larger of the length passed into tpalloc() and the default specified in dfltsize() in that type's switch entry. Note that ptr will never be NULL due to the semantics of tpalloc() and tprealloc(). Upon successful return, ptr is returned to the caller of tpalloc().

If a single switch entry is used to manipulate many subtypes, then the writer of tminitbuf() can use tptypes() to determine the subtype.

If no buffer initialization needs to be performed, specify a NULL function pointer.

Upon success, _tminitbuf() returns 1. If the function fails, it returns -1 causing tpalloc() to also return failure setting tperrno to TPESYSTEM.

tmreinitbuf

_tmreinitbuf() behaves the same as _tminitbuf() except it is used to reinitialize a reallocated buffer. It is called from within tprealloc() after the buffer has been reallocated.

If no buffer reinitialization needs to be performed, specify a NULL function pointer.

Upon success, _tmreinitbuf() returns 1. If the function fails, it returns -1 causing tprealloc() to also return failure setting tperrno to TPESYSTEM.

tmuninitbuf

_tmuninitbuf() is called by tpfree() before the data buffer is freed.
_tmuninitbuf() is passed a pointer to the application portion of a data buffer, along with its size, and can be used to clean up any structures or state information associated with that buffer. ptr will never be NULL due to tpfree()'s semantics. Note that _tmuninitbuf() should not free the buffer itself. The tpfree() function is called automatically for any FLD_PTR fields in the data buffer.

If no processing needs to be performed before freeing a buffer, specify a NULL function pointer.

Upon success, _tmuninitbuf() returns 1. If the function fails, it returns -1 causing tpfree() to print a log message.

_tmpresend

_tmpresend() is called before a buffer is sent in tpcall(), tpacall(), tpconnect(), tpsend(), tpbroadcast(), tpnotify(), tpreturn(), or tpforward(). It is also called after _tmroute() but before _tmencdec(). If ptr() is non-NULL, preprocessing is performed on a buffer before it is sent. _tmpresend()'s first argument, ptr, is the application data buffer passed into the send call. Its second argument, dlen, is the data's length as passed into the send call. Its third argument, mdlen, is the actual size of the buffer in which the data resides.

One important requirement on this function is that it ensures that when the function returns, the data pointed to by ptr can be sent "as is." That is, since $_tmencdec()$ is called only if the buffer is being sent to a dissimilar machine, $_tmpresend()$ must ensure upon return that no element in ptr's buffer is a pointer to data that is not contiguous to the buffer.

If no preprocessing needs to be performed on the data and the amount of data the caller specified is the same as the amount that should be sent, specify a NULL function pointer. The default routine returns <code>dlen</code> and does nothing to the buffer.

If _tmpresend2() is not NULL, _tmpresend() is not called and _tmpresend2() is called in its place.

Upon success, _tmpresend() returns the amount of data to be sent. If the function fails, it returns -1 causing _tmpresend() 's caller to also return failure setting tperrno to TPESYSTEM.

_tmpostsend

_tmpostsend() is called after a buffer is sent in tpcall(), tpbroadcast(), tpnotify(), tpacall(), tpconnect(), or tpsend(). This routine allows any post-processing to be performed on a buffer after it is sent and before the function returns. Because the buffer passed into the send call should not be different upon return, _tmpostsend() is called to repair a buffer changed by _tmpresend(). This function's first argument, ptr, points to the data sent as a result of _tmpresend(). The data's length, as returned from _tmpresend(), is passed in as this function's second argument, dlen. The third argument, mdlen, is the actual size of the buffer in which the data resides. This routine is called only when ptr is non-NULL.

If no post-processing needs to be performed, specify a NULL function pointer.

_tmpostrecv

_tmpostrecv() is called after a buffer is received, and possibly decoded, in tpgetrply(), tpcall(), tprecv(), or in the BEA Tuxedo ATMI system's server abstraction, and before it is returned to the application. If ptr is non-NULL, _tmpostrecv() allows post-processing to be performed on a buffer after it is received and before it is given to the application. Its first argument, ptr, points to the data portion of the buffer received. Its second argument, dlen, specifies the data's size coming in to _tmpostrecv(). The third argument, mdlen, specifies the actual size of the buffer in which the data resides.

If _tmpostrecv() changes the data length in post-processing, it must return the data's new length. The length returned is passed up to the application in a manner dependent on the call used (for example, tpcall() sets the data length in one of its arguments for the caller to check upon return).

The buffer's size might not be large enough for post-processing to succeed. If more space is required, _tmpostrecv() returns the negative absolute value of the desired buffer size. The calling routine then resizes the buffer, and calls _tmpostrecv() a second time.

If no post-processing needs to be performed on the data and the amount of data received is the same as the amount that should be returned to the application, specify a NULL function pointer. The default routine returns <code>dlen</code> and does nothing to the buffer.

On success, _tmpostrecv() returns the size of the data the application should be made aware of when the buffer is passed up from the corresponding receive call. If the function fails, it returns -1 causing _tmpostrecv() 's caller to return failure, setting tperrno to TPESYSTEM.

_tmencdec

_tmencdec() is used to encode/decode a buffer sent/received over a network to/from a machine having different data representations. The BEA Tuxedo ATMI system recommends the use of XDR; however, any encoding/decoding scheme can be used that obeys the semantics of this routine.

This function is called by tpcall(), tpacall(), tpbroadcast(), tpnotify(), tpconnect(), tpsend(), tpreturn(), or tpforward() to encode the caller's buffer only when it is being sent to an "unlike" machine. In these calls, _tmencdec() is called after both _tmroute() and _tmpresend(), respectively. Recall from the description of _tmpresend() that the buffer passed into _tmencdec() contains no pointers to data that is not contiguous to the buffer.

On the receiving end, tprecv(), tpgetrply(), the receive half of tpcall() and the server abstraction all call_tmencdec() to decode a buffer after they have received it from an "unlike" machine but before calling tmpostrecv().

_tmencdec()'s first argument, op, specifies whether the function is encoding or decoding data. op can be one of TMENCODE or TMDECODE.

When op is TMENCODE, encobj points to a buffer allocated by the BEA Tuxedo ATMI system where the encoded version of the data will be copied. The unencoded data resides in obj. That is, when op is TMENCODE, _tmencdec() transforms obj to its encoded format and places the result in encobj. The size of the buffer pointed to by encobj is specified by elen and is at least four times the size of the buffer pointed to by obj whose length is olen. olen is the length returned by _tmpresend. _tmencdec() returns the size of the encoded data in encobj (that is, the amount of data to actually send). _tmencdec() should not free either of the buffers passed into the function

When <code>op</code> is <code>TMDECODE</code>, <code>encobj</code> points to a buffer allocated by the BEA Tuxedo ATMI system where the encoded version of the data resides as read off a communication endpoint. The length of the buffer is <code>elen.obj</code> points to a buffer that is at least the same size as the buffer pointed to by <code>encobj</code> into which the decoded data is copied. The length of <code>obj</code> is <code>olen</code>. As <code>obj</code> is the buffer ultimately returned to the application, this buffer may be grown by the BEA Tuxedo ATMI system before calling <code>_tmencdec()</code> to ensure that it is large enough to hold the decoded data. <code>_tmencdec()</code> returns the size of the decoded data in <code>obj</code>. After <code>_tmencdec()</code> returns,

_tmpostrecv() is called with obj passed as its first argument, _tmencdec()'s return value as its second, and olen as its third. _tmencdec() should not free either of the buffers passed into the function.

tmencdec() is called only when non-NULL data needs to be encoded or decoded.

If no encoding or decoding needs to be performed on the data even when dissimilar machines exist in the network, specify a NULL function pointer. The default routine returns either olen (op equals TMENCODE) or elen (op equals TMDECODE).

On success, _tmencdec() returns a non-negative length as described above. If the function fails, it returns -1 causing _tmencdec()'s caller to return failure, setting tperrno to TPESYSTEM.

tmroute

The default for message routing is to route a message to any available server group that offers the desired service. Each service entry in the UBBCONFIG file can specify the logical name of some routing criteria for the service using the ROUTING parameter. Multiple services can share the same routing criteria. In the case that a service has a routing criteria name specified, _tmroute() is used to determine the server group to which a message is sent based on data in the message. This mapping of data to server group is called "data-dependent routing." _tmroute() is called before a buffer is sent (and before _tmpresend() and _tmencdec() are called) in tpcall(), tpacall(), tpconnect(), and tpforward().

routing_name is the logical name of the routing criteria (as specified in the UBBCONFIG file) and is associated with every service that needs data dependent routing. service is the name of the service for which the request is being made. The parameter data points to the data that is being transmitted in the request and len is its length. Unlike the other routines described in these pages, _tmroute() is called even when ptr is NULL. The group parameter is used to return the name of the group to which the request should be routed. This group name must match one of the group names listed in the UBBCONFIG file (and one that is active at the time the group is chosen). If the request can go to any available server providing the specified service, group should be set to the NULL string and the function should return 1.

If data dependent routing is not needed for the buffer type, specify a NULL function pointer. The default routine sets *group* to the NULL string and returns 1.

Upon success, _tmroute() returns 1. If the function fails, it returns -1 causing _tmroute()'s caller to also return failure; as a result, tperrno is set to TPESYSTEM. If _tmroute() fails because a requested server or service is not available, tperrno is set to TPENOENT.

If group is set to the name of an invalid server group, the function calling _tmroute() will return an error and set tperrno to TPESYSTEM.

tmfilter

_tmfilter() is called by the EventBroker server to analyze the contents of a buffer posted by tppost(). An expression provided by the subscriber(tpsubscribe()) is evaluated with respect to the buffer's contents. If the expression is true, _tmfilter() returns 1 and the EventBroker performs the subscription's notification action. Otherwise, if _tmfilter() returns 0, the EventBroker does not consider this posting a "match" for the subscription.

If exprlen is -1, expr is interpreted as a NULL-terminated character string. Otherwise expr is interpreted as exprlen bytes of binary data. An exprlen of 0 indicates no expression.

If filtering does not apply to this buffer type, specify a NULL function pointer. The default routine returns 1 if there is no expression or if *expr* is an empty NULL-terminated string. Otherwise the default routine returns 0.

tmformat

_tmformat() is called by the EventBroker server to convert a buffer's data into a printable string, based on a format specification named fmt. The EventBroker converts posted buffers to strings as input for userlog or system notification actions.

The output is stored as a character string in the memory location pointed to by result. Up to maxresult bytes are written in result, including a terminating NULL character. If result is not large enough, _tmformat() truncates its output. The output string is always NULL terminated.

On success, _tmformat() returns a non-negative integer. 1 means success, 2 means the output string is truncated. If the function fails, it returns -1 and stores an empty string in result.

If formatting does not apply to this buffer type, specify a NULL function pointer. The default routine succeeds and returns an empty string in result.

tmpresend2

_tmpresend2() is called before a buffer is sent in tpcall(), tpacall(), tpconnect(), tpsend(), tpbroadcast(), tpnotify(), tpreturn(), and tpforward(). It is also called after _tmroute() but before _tmencdec(). If iptr is not NULL, preprocessing is performed on a buffer before the buffer is sent.

The first argument to _tmpresend2(), iptr, is the application data buffer passed into the send call. The second argument, ilen, is the length of the data as passed into the send call. The third argument, mdlen, is the actual size of the buffer in which the data resides.

Unlike _tmpresend(), _tmpresend2() receives a pointer, optr, which is used to pass a pointer to a buffer into which the data in iptr can be placed, after any required processing is done. Use this pointer if you want to use a new buffer for the data modified by _tmpresend2() instead of modifying the input buffer. The fifth argument, olen, is the size of the optr buffer. The sixth argument, flags, tells _tmpresend2() whether the buffer being processed is the parent buffer (the one being sent). The flags argument is returned by _tmpresend2() to indicate the results of processing.

The size of the <code>optr</code> buffer may not be large enough for successful postprocessing. If more space is required, <code>_tmpresend2()</code> returns the negative absolute value of the desired buffer size. All <code>olen</code> bytes of the <code>optr</code> buffer are preserved. The calling routine then resizes the buffer and calls <code>tmpresend2()</code> a second time.

If no postprocessing needs to be performed on the data, and the amount of data received is the same as the amount that should be returned to the application, specify a NULL function pointer. The default routine returns *ilen* and does not modify the buffer

The following is a valid flag on input to tmpresend2():

[TMPARENT]

This is the parent buffer (the one being sent).

The flags returned in flags specify the results of _tmpresend2(). Possible values are:

[TMUSEIPTR]

_tmpresend2() was successful: the processed data is in the buffer referenced by *iptr*, and the return value contains the length of the data to be sent.

[TMUSEOPTR]

_tmpresend2() was successful: the processed data is in the buffer referenced by optr, and the return value contains the length of the data to be sent.

If TMUSEOPTR is returned, the processing done after messages are transmitted is different from the processing done by _tmpresend(): the *iptr* buffer remains unchanged and _tmpostsend() is not called. If TMUSEIPTR is returned, _tmpostsend() is called, as it is called for _tmpresend(). It is the responsibility of the caller to allocate and to free or cache the <code>optr</code> buffer.

There are several reasons why you may want to use this approach for a typed buffer:

- The buffer created by processing for transmission is larger than the maximum length allowed for the input buffer.
- Undoing the processing to prepare a buffer for transmission is so complicated that it is easier to copy the data to a different buffer.

The _tmpresend2 () function ensures that when a function returns, the data in the buffer to be sent can be sent without further processing. Because _tmencdec() is called only if the buffer is being sent to a dissimilar machine, _tmpresend2() ensures, upon return, that all data is stored contiguously in the buffer to be sent.

If no preprocessing needs to be performed on the data, and the amount of data specified by the caller is the same as the amount that should be sent, specify a NULL function pointer for _tmpresend2() in the buffer type switch. If _tmpresend2() is NULL, tmpresend() is called by default.

Upon success, _tmpresend2() returns the amount of data to be sent or, if a larger buffer is needed, the negative absolute value of the desired buffer size. If the function fails, it returns -1, causing the caller of _tmpresend2() to also return failure, setting tperrno to TPESYSTEM.

tmconvmb

_tmconvmb() is called after tmpostrecv() to convert multibyte data from a source encoding to a target encoding. The first argument to _tmconvmb(), ibufp, is a pointer to a stream of bytes—the multibyte data—to be converted. The second argument, ilen, is the number of bytes in ibufp. The third argument, enc_name, is one of the encoding names used in the processing. For an MBSTRING buffer, the third argument is the target encoding name; for an FML32 buffer, the third argument is the source encoding name.

_tmconvmb() receives a pointer, <code>obufp</code>, which is used to pass a pointer to a buffer into which the data in <code>ibufp</code> can be placed, after any required code-set encoding conversion is done. Use this pointer if you want to use a new buffer for the data converted by <code>_tmconvmb()</code> instead of modifying the input pointer. The fifth argument, <code>olen</code>, is the size of the <code>obufp</code> buffer. The <code>flags</code> argument is returned by <code>tmconvmb()</code> to indicate the results of processing.

The size of the <code>obufp</code> buffer may not be large enough for successful post processing. If more space is required, <code>_tmconvmb()</code> returns the negative absolute value of the desired buffer size. All <code>ilen</code> bytes of the <code>ibufp</code> buffer are preserved. The calling routine then resizes the buffer and calls <code>_tmconvmb()</code> a second time.

If no code-set encoding conversion needs to be performed on the data, and the encoding name of the sending process is the same as the encoding name of the receiving process, specify a NULL function pointer. The default routine returns *ilen* and does not convert the buffer. If this function does not know how to convert the code-set encoding, it returns -1.

The value returned in flags specifies the result of _tmconvmb(). Possible values are:

[TMUSEIPTR]

_tmconvmb() was successful: the processed data is in the buffer referenced by *ibufp*, and the return value contains the length of the converted data to be passed to the service.

[TMUSEOPTR]

_tmconvmb() was successful: the processed data is in the buffer referenced by obufp, and the return value contains the length of the data to be converted. It is the responsibility of the caller to allocate and to free or cache the obufp buffer

Upon success, _tmconvmb() returns the amount of data buffer that had code-set encoding conversion or, if a larger buffer is needed, the negative absolute value of the desired buffer size. If the function fails, it returns -1, causing the caller of _tmconvmb() to also return failure, setting tperrno to TPESYSTEM.

See Also

```
tpacall(3c), tpalloc(3c), tpcall(3c), tpconnect(3c), tpdiscon(3c),
tpfree(3c), tpgetrply(3c), tpgprio(3c), tprealloc(3c), tprecv(3c),
tpsend(3c), tpsprio(3c), tptypes(3c), tuxtypes(5)
```

catgets(3c)

Name catgets ()—Reads a program message.

Synopsis #include <nl_types.h>

char *catgets (nl catd catd, int set num, int msg num, char *s)

Description catgets () attempts to read message msg num, in set set num, from the message

catalogue identified by catd. catd is a catalogue descriptor returned from an earlier call to catopen(). s points to a default message string which will be returned by

catgets () if the identified message catalogue is not currently available.

A thread in a multithreaded application may issue a call to catgets () while running

in any context state, including TPINVALIDCONTEXT.

Diagnostics If the identified message is retrieved successfully, catgets () returns a pointer to an

internal buffer area containing the NULL terminated message string. If the call is unsuccessful because the message catalogue identified by catd is not currently

available, a pointer to s is returned.

See Also catopen, catclose(3c)

catopen, catclose(3c)

Name catopen(), catclose()—Opens/closes a message catalogue.

Description

catopen () opens a message catalogue and returns a catalogue descriptor. name specifies the name of the message catalogue to be opened. If name contains a "/" then name specifies a pathname for the message catalogue. Otherwise, the environment variable NLSPATH is used. If NLSPATH does not exist in the environment, or if a message catalogue cannot be opened in any of the paths specified by NLSPATH, then the default path is used (see nl types (5)).

The names of message catalogues, and their location in the filestore, can vary from one system to another. Individual applications can choose to name or locate message catalogues according to their own special needs. A mechanism is therefore required to specify where the catalogue resides.

The NLSPATH variable provides both the location of message catalogues, in the form of a search path, and the naming conventions associated with message catalogue files. For example:

NLSPATH=/nlslib/%L/%N.cat:/nlslib/%N/%L

The metacharacter % introduces a substitution field, where %L substitutes the current setting of the LANG environment variable (see following section), and %N substitutes the value of the name parameter passed to catopen(). Thus, in the above example, catopen() will search in /nlslib/\$LANG/name.cat, then in /nlslib/name/\$LANG, for the required message catalogue.

NLSPATH will normally be set up on a system wide basis (for example, in /etc/profile) and thus makes the location and naming conventions associated with message catalogues transparent to both programs and users.

The following table lists the full set of metacharacters.

Metacharacter	Description
%N	The value of the name parameter passed to catopen.
%L	The value of LANG.

%1	The value of the language element of LANG.
%t	The value of the territory element of LANG.
%C	The value of the codeset element of LANG.
% %	A single %.

The LANG environment variable provides the ability to specify the user's requirements for native languages, local customs and character set, as an ASCII string in the form LANG=language[territory[.codeset]]

A user who speaks German as it is spoken in Austria and has a terminal that operates in ISO 8859/1 codeset, would want the setting of the LANG variable to be as follows:

LANG=De_A.88591

With this setting it should be possible for the user to find relevant catalogues if they exist.

If the LANG variable is not set then the value of LC_MESSAGES as returned by setlocale(3c) is used. If this is NULL then the default path as defined in nl types(5) is used.

oflag() is reserved for future use and should be set to 0. The results of setting this field to any other value are undefined.

catclose() closes the message catalogue identified by catd.

A thread in a multithreaded application may issue a call to catopen() or catclose() while running in any context state, including TPINVALIDCONTEXT.

Diagnostics

If successful, catopen() returns a message catalogue descriptor for use on subsequent calls to catgets() and catclose(). Otherwise catopen() returns (nl_catd) -1. catclose() returns 0 if successful, otherwise -1.

See Also catgets (3c), setlocale (3c), nl_types (5)

decimal(3c)

Name decimal()—Decimal conversion and arithmetic routines.

Synopsis

```
#include "decimal.h"
int
lddecimal(cp, len, np) /* load a decimal */
             /* input: location of compacted format */
int
len;
                /* input: length of compacted format */
dec t*np;  /* output: location of dec t format */
void
stdecimal(np, cp, len)
                              /* store a decimal */
char*cp;  /* output: location of compacted format */
int len;  /* input: length of compacted format */
int
\label{eq:compare} \mbox{deccmp(n1, n2)} \qquad / * \mbox{compare two decimal numbers } */
dec t*n1; /* input: number to be compared */
dec t*n2; /* input: number to be compared */
int
dectoasc(np, cp, len, right) /* convert dec t to ascii */
dec_t*np;    /* input: number to be converted */
char*cp;    /* output: number after conversion */
int len;    /* input: length of output string */
int right;    /* input: number of places to right of decimal point */
deccvasc(cp, len, np)
                              /* convert ascii to dec t */
int
dectoint(np, ip)
                              /* convert int to dec t */
int.
deccvint(in, np) /* convert dec t to int */
              /* input: number to be converted */
/* output: number after conversion */
int in;
dec_t*np;
```

```
int
dectolong(np, lngp) /* convert dec_t to long */
int.
deccvlong(lng, np) /* convert long to dec t */
int.
dectodbl(np, dblp) /* convert dec t to double */
dec_t*np; /* input: number to be converted */
double *dblp; /* output: number after conversion */
int.
deccvdbl(dbl, np) /* convert double to dec t */
double *dbl;  /* input: number to be converted */
dec_t*np;  /* output: number after conversion */
int.
dectoflt(np, fltp) /* convert dec_t to float */
int.
deccvflt(flt, np) /* convert float to dec t */
double *flt; /* input: number to be converted \bar{*}/
dec t*np;  /* output: number after conversion */
int
decadd(*n1, *n2, *n3) /* add two decimal numbers */
dec_t*n1; /* input: addend */
dec_t*n2; /* input: addend */
dec_t*n3; /* output: sum */
int
decsub(*n1, *n2, *n3) /* subtract two decimal numbers */
dec_t*n1;  /* input: minuend */
dec_t*n2;  /* input: subtrahend */
dec_t*n3;  /* output: difference */
int.
decmul(*n1, *n2, *n3) /* multiply two decimal numbers */
decdiv(*n1, *n2, *n3) /* divide two decimal numbers */
dec t*n1; /* input: dividend */
```

```
dec_t*n2;  /* input: divisor */
dec t*n3;  /* output: quotient */
```

Description

These functions allow storage, conversion, and manipulation of packed decimal data on the BEA Tuxedo ATMI system. Note that the format in which the decimal data type is represented on the BEA Tuxedo ATMI system is different from its representation under CICS.

A thread in a multithreaded application may issue a call to any of the decimal conversion functions while running in any context state, including TPINVALIDCONTEXT.

Native Decimal Representation

Decimals are represented on native BEA Tuxedo ATMI system nodes using the dec_t structure. This definition of this structure is as follows:

It should never be necessary for programmers to directly access the dec_t structure, but it is presented here nevertheless to give an understanding of the underlying data structure. If large amounts of decimal data need to be stored, the stdecimal() and lddecimal() functions may be used to obtain a more compact format. dectoasc(), dectoint(), dectolong(), dectodbl(), and dectoflt() allow the conversion of decimals to other data types. deccvasc(), deccvint(), deccvlong(), deccvdbl(), and deccvflt() allow the conversion of other data types to the decimal data type. deccmp() is the function which compares two decimals. It returns -1 if the first decimal is less than the second, 0 if the two decimals are equal, and 1 if the first decimal is greater than the second. A negative value other than -1 is returned if either of the arguments is invalid. decadd(), decsub(), decmul(), and decdiv() perform arithmetic operations on decimal numbers.

Return Value

Unless otherwise stated, these functions return 0 on success and a negative value on error.

getURLEntityCacheDir(3c)

Name getURLEntityCacheDir () - method for getting the absolute path to the location

where the DTD, schema and Entity files are cached.

Synopsis char * getURLEntityCacheDir ()

Description geturlEntityCacheDir() is invoked when the caller needs to find out the location

where the DTD, schema and Entity files are cached. It returns the absolute path to the

cached file location.

GetURLEntityCaching(3c)

Name GetURLEntityCaching() - method for getting the caching mechanism for DTD,

schema and Entity files.

Synopsis bool getURLEntityCaching()

Description This method is invoked when the caller wants to find out if caching of DTD, schema

and Entity files are turned on or off. It returns true if caching is turned on and false if

caching is turned off.

gp_mktime(3c)

Name gp mktime()—Converts a tm structure to a calendar time.

```
Synopsis #include <time.h>
    time t gp mktime (struct tm *timeptr);
```

Description

gp_mktime() converts the time represented by the tm structure pointed to by timeptr into a calendar time (the number of seconds since 00:00:00 Universal Coordinated Time—UTC, January 1, 1970).

The tm structure has the following format:

In addition to computing the calendar time, <code>gp_mktime()</code> normalizes the supplied <code>tm</code> structure. The original values of the <code>tm_wday</code> and <code>tm_yday</code> components of the structure are ignored, and the original values of the other components are not restricted to the ranges indicated in the definition of the structure. On successful completion, the values of the <code>tm_wday</code> and <code>tm_yday</code> components are set appropriately, and the other components are set to represent the specified calendar time, but with their values forced to be within the appropriate ranges. The final value of <code>tm_mday</code> is not set until <code>tm_mon</code> and <code>tm_year</code> are determined.

The original values of the components may be either greater than or less than the specified range. For example, a tm_hour of -1 means 1 hour before midnight, tm_mday of 0 means the day preceding the current month, and tm_mon of -2 means 2 months before January of tm_year .

If tm_isdst is positive, the original values are assumed to be in the alternate time zone. If it turns out that the alternate time zone is not valid for the computed calendar time, then the components are adjusted to the main time zone. Likewise, if tm_isdst is zero, the original values are assumed to be in the main time zone and are converted to the alternate time zone if the main time zone is not valid. If tm_isdst is negative, the correct time zone is determined and the components are not adjusted.

Local time zone information is used as if gp mktime() had called tzset().

gp_mktime() returns the specified calendar time. If the calendar time cannot be represented, the function returns the value (time t)-1.

A thread in a multithreaded application may issue a call to <code>gp_mktime()</code> while running in any context state, including <code>TPINVALIDCONTEXT</code>.

Example What day of the week is July 4, 2001?

```
#include <stdio.h>
#include <time.h>
static char *const wday[] = {
"Sunday", "Monday", "Tuesday", "Wednesday",
"Thursday", "Friday", "Saturday", "-unknown-"
};
struct tm time str;
/*...*/
time_str.tm_mon
time_str.tm_mday
time_str.tm_hour
                     = 4;
                     = 0;
time str.tm min
                      = 0;
time str.tm sec
                      = 1;
time str.tm isdst = -1;
if (gp \ mktime(time \ str) == -1)
   time str.tm wday=7;
printf("%s\en", wday[time_str.tm_wday]);
```

Notices

tm_year of the tm structure must be for year 1970 or later. Calendar times before 00:00:00 UTC, January 1, 1970 or after 03:14:07 UTC, January 19, 2038 cannot be represented.

Portability

On systems where the C compilation system already provides the ANSI C mktime() function, $gp_mktime()$ simply calls mktime() to do the conversion. Otherwise, the conversion is provided directly in $gp_mktime()$.

In the latter case, the TZ environment variable must be set. Note that in many installations, TZ is set to the correct value by default when the user logs on. The default value for TZ is GMTO. The format for TZ is the following:

```
stdoffset[dst[offset],[start[time],end[time]]]
```

std and dst

Three or more bytes that designate the standard time zone (std) and daylight savings time time zone (dst). Only std is required. If dst is missing, then daylight savings time does not apply in this locale. Uppercase and lowercase letters are allowed. Any characters except a leading colon (:), digits, a comma (,), a minus (-) or a plus (+) are allowed.

offset

Indicates the value one must add to the local time to arrive at Coordinated Universal Time. The <code>offset</code> has the following form: <code>hh[:mm[:ss]]</code>. The minutes (<code>mm</code>) and seconds (<code>ss</code>) are optional. The hour (<code>hh</code>) is required and may be a single digit. The <code>offset</code> following <code>std</code> is required. If no <code>offset</code> follows <code>dst</code>, daylight savings time is assumed to be one hour ahead of standard time. One or more digits may be used; the value is always interpreted as a decimal number. The hour must be between 0 and 24, and the minutes (and seconds) if present, between 0 and 59. Out of range values may cause unpredictable behavior. If preceded by a "-", the time zone is east of the Prime Meridian; otherwise it is west (which may be indicated by an optional preceding "+" sign).

start/time,end/time

Indicates when to change to and back from daylight savings time, where <code>start/time</code> describes when the change from standard time to daylight savings time occurs, and <code>end/time</code> describes when the change back happens. Each <code>time</code> field describes when, in current local time, the change is made. The formats of <code>start</code> and <code>end</code> are one of the following:

 \mathbf{J}_n

The Julian day n (1 n 365). Leap days are not counted. That is, in all years, February 28 is day 59 and March 1 is day 60. It is impossible to refer to the occasional February 29.

n

The zero-based Julian day (0 n 365). Leap days are counted, and it is possible to refer to February 29.

 $M_{m.n.d}$

Day $a(0 \ a \ 6)$ of week n of month m in the year $(1 \ n \ 5, 1 \ m \ 12)$, where week 5 means "the last a-day in month m," which may occur in either the fourth or the fifth week). Week 1 is the first week in which day a occurs. Day 0 (zero) is Sunday.

Implementation specific defaults are used for start and end if these optional fields are not given.

The time has the same format as offset except that no leading sign ("-" or "+") is allowed. The default, if time is not specified, is 02:00:00.

See Also ctime(3c), getenv(3c), timezone(4) in a UNIX system reference manual

nl_langinfo(3c)

Name nl langinfo()—Language information.

Synopsis #include <nl_types.h>
 #include <langinfo.h>

char *nl langinfo (nl item item);

Description

nl_langinfo() returns a pointer to a NULL-terminated string containing information relevant to a particular language or cultural area defined in the programs locale. The manifest constant names and values of *item* are defined by langinfo.h.

For example:

nl langinfo (ABDAY 1);

returns a pointer to the string "Dim" if the identified language is French and a French locale is correctly installed; or "Sun" if the identified language is English.

A thread in a multithreaded application may issue a call to nl_langinfo() while running in any context state, including TPINVALIDCONTEXT.

Diagnostics

If setlocale() has not been called successfully, or if langinf0() data for a supported language is either not available or *item* is not defined therein, then nl_langinfo() returns a pointer to the corresponding string in the C locale. In all locales, nl_langinfo() returns a pointer to an empty string if *item* contains an invalid setting.

Notices

The array pointed to by the return value should not be modified by the program. Subsequent calls to nl langinfo() may overwrite the array.

See Also setlocale(3c), strftime(3c), langinfo(5), nl_types(5)

rpc_sm_allocate, rpc_ss_allocate(3c)

Name rpc_sm_allocate(), rpc_ss_allocate()—Allocates memory within the RPC stub memory management scheme.

Synopsis #include <rpc/rpc.h>
 idl_void_p_t rpc_sm_allocate(unsigned32 size, unsigned32 *status)
 idl void p t rpc ss allocate(unsigned32 size)

Description Applications call <code>rpc_sm_allocat3()</code> to allocate memory within the RPC stub memory management scheme. The input parameter, <code>size</code>, specifies in bytes, the size of memory to be allocated. Before a call to this routine, the stub memory management environment must have been established. For service code that is called from the server stub, the stub itself normally establishes the necessary environment. When <code>rpc_sm_allocate()</code> is used by code that is not called from the stub, the application must establish the required memory management environment by calling <code>rpc_sm_enable_allocate()</code>.

Specifically, if the parameters of a server stub include any pointers other than those used for passing parameters by reference or the <code>[enable_allocate]</code> attribute is specified for the operation in the ACS file, then the environment is automatically set up. Otherwise, the environment must be set up by the application by calling <code>rpc sm enable allocate()</code>.

When the stub establishes the memory management environment, the stub itself frees any memory allocated by rpc_sm_allocate(). The application can free such memory before returning to the calling stub by calling rpc sm free().

When the application establishes the memory management environment, it must free any memory allocated, either by calling rpc_sm_free() or by calling rpc_sm_disable_allocate().

The output parameter, status, returns the status code from this routine. This status code indicates whether the routine completed successfully or, if not, why not. Possible status codes and their meanings include:

```
rpc_s_ok
Always returned. The return value is used to determine failure.
```

rpc_ss_allocate() is the exception-returning version of this function and has no status output parameter. No exceptions are raised.

A thread in a multithreaded application may issue a call to <code>rpc_sm_allocate()</code> or <code>rpc_ss_allocate()</code> while running in any context state, including <code>TPINVALIDCONTEXT</code>.

Return Values

Upon success, the routines return a pointer to the allocated memory. Note that in the ISO standard C environments, idl_void_p_t is defined as void * and in other environments it is defined as char *.

If there is insufficient memory, the routines return a NULL pointer.

See Also

```
rpc_sm_disable_allocate, rpc_ss_disable_allocate(3c),
rpc_sm_enable_allocate, rpc_ss_enable_allocate(3c), rpc_sm_free,
rpc_ss_free(3c)
```

rpc_sm_client_free, rpc_ss_client_free(3c)

Name

rpc_sm_client_free(), rpc_ss_client_free() —Frees memory returned from a
client stub.

Synopsis

```
#include <rpc/rpc.h>
void rpc_sm_client_free (idl_void_p_t node_to_free, unsigned32 *status)
void rpc_ss_client_free (idl_void_p_t node_to_free)
```

Description

The rpc_sm_client_free() routine releases memory allocated and returned from a client stub. The input parameter, node_to_free, specifies a pointer to memory returned from a client stub. Note that in the ISO standard C environments, idl void p t is defined as void * and in other environments is defined as char *.

This routine enables a routine to deallocate dynamically allocated memory returned by an RPC call without knowledge of the memory management environment from which it was called.

Note that this routine is always called from client code, even if the code can is executing as part of a server.

The output parameter, <code>status</code>, returns the status code from this routine. This status code indicates whether the routine completed successfully or, if not, why not. Possible status codes and their meanings include:

```
rpc_s_ok
Success.
```

rpc_ss_client_free() is the exception-returning version of this function and has no status output parameter. No exceptions are raised.

A thread in a multithreaded application may issue a call to rpc_sm_client_free() or rpc_ss_client_free() while running in any context state, including
TPINVALIDCONTEXT

Return Values None.

rpc_sm_disable_allocate, rpc_ss_disable_allocate(3c)

Name rpc_sm_disable_allocate(), rpc_ss_disable_allocate()—Releases resources and allocated memory within the stub memory management scheme.

Synopsis #include <rpc/rpc.h>
 void rpc_sm_disable_allocate(unsigned32 *status);
 void rpc ss disable allocate(void);

Description The rpc_sm_disable_allocate() routine releases all resources acquired by a call to rpc_sm_enable_allocate(), and any memory allocated by calls to rpc_sm_allocate() after the call to rpc_sm_enable_allocate() was made.

The $rpc_sm_enable_allocate()$ and $rpc_sm_disable_allocate()$ routines must be used in matching pairs. Calling this routine without a previous matching call to $rpc_sm_enable_allocate()$ results in unpredictable behavior.

The output parameter, status, returns the status code from this routine. This status code indicates whether the routine completed successfully or, if not, why not. Possible status codes and their meanings include:

```
rpc_s_ok
Success.
```

rpc_ss_disable_allocate() is the exception-returning version of this function and has no status output parameter. No exceptions are raised.

A thread in a multithreaded application may issue a call to rpc_sm_disable_allocate() or rpc_ss_disable_allocate() while running in any context state, including TPINVALIDCONTEXT.

Return Values None.

See Also rpc_sm_allocate, rpc_ss_allocate(3c), rpc_sm_enable_allocate, rpc_ss_enable_allocate(3c)

rpc_sm_enable_allocate, rpc_ss_enable_allocate(3c)

 $\label{locate} \textbf{Name} \qquad \texttt{rpc_sm_enable_allocate(), rpc_ss_enable_allocate()} \\ -Enables \ the \ stub$

memory management environment.

Synopsis #include <rpc/rpc.h>

void rpc_sm_enable_allocate(unsigned32 *status)

void rpc ss enable allocate (void)

Description

Applications can call <code>rpc_sm_enable_allocate()</code> to establish a stub memory management environment in cases where one is not established by the stub itself. A stub memory management environment must be established before any calls are made to <code>rpc_sm_allocate()</code>. For service code called from the server stub, the stub memory management environment is normally established by the stub itself. Code that is called from other contexts needs to call <code>rpc_sm_enable_allocate()</code> before calling <code>rpc_sm_allocate()</code> (for example, if the service code is called directly instead of from the stub).

The output parameter, status, returns the status code from this routine. This status code indicates whether the routine completed successfully or, if not, why not. Possible status codes and their meanings include:

```
rpc_s_ok
Success.
```

```
rpc s no memory
```

Insufficient memory available to set up necessary data structures.

rpc_ss_enable_allocate() is the exception-returning version of this function and has no status output parameter. The following exceptions are raised by this routine:

```
rpc x no memory
```

Insufficient memory available to set up necessary data structures.

A thread in a multithreaded application may issue a call to

rpc_sm_enable_allocate() or rpc_ss_enable_allocate() while running in any context state, including TPINVALIDCONTEXT.

Return Values None.

See Also rpc_sm_allocate, rpc_ss_allocate(3c), rpc_sm_disable_allocate, rpc ss disable allocate(3c)

rpc_sm_free, rpc_ss_free(3c)

Name rpc_sm_free, rpc_ss_free()—Frees memory allocated by the rpc sm allocate() routine.

Synopsis #include <rpc/rpc.h>

void rpc_sm_free(idl_void_p_t node_to_free, unsigned32 *status)
void rpc ss free(idl void p t node to free)

Description

Applications call rpc_sm_free() to release memory allocated by rpc_sm_allocate(). The input parameter, node_to_free, specifies a pointer to memory allocated by rpc_sm_allocate(). Note that in ISO standard C environments, idl_void_p_t is defined as void * and in other environments is defined as char *.

When the stub allocates memory within the stub memory management environment, service code called from the stub can also use rpc_sm_free() to release memory allocated by the stub.

Unpredictable behavior results if rpc_ss_free() is called with a pointer to memory not allocated by rpc_sm_allocate() or memory allocated by rpc_sm_allocate(), but not the first address of such an allocation.

The output parameter, status, returns the status code from this routine. This status code indicates whether the routine completed successfully or, if not, why not. Possible status codes and their meanings include:

```
rpc_s_ok
Success.
```

rpc_ss_free is the exception-returning version of this function and has no status output parameter. No exceptions are raised.

A thread in a multithreaded application may issue a call to $rpc_sm_free()$ or $rpc_ss_free()$ while running in any context state, including TPINVALIDCONTEXT.

Return Values None.

```
See Also rpc_sm_allocate, rpc_ss_allocate(3c)
```

rpc_sm_set_client_alloc_free, rpc_ss_set_client_alloc_free(3c)

Name rpc_sm_set_client_alloc_free(),rpc_ss_set_client_alloc_free()—Sets the memory allocation and freeing mechanisms used by the client stubs.

Synopsis

```
#include <rpc/rpc.h>
void rpc_sm_set_client_alloc_free(
   idl_void_p_t (*p_allocate) (unsigned long size),
   void (*p_free) (idl_void_p_t ptr), unsigned32 *status)

void rpc_ss_set_client_alloc_free(
   idl_void_p_t (*p_allocate) (unsigned long size),
   void (*p_free) (idl_void_p_t ptr))
```

Description

The rpc_sm_set_client_alloc_free() routine overrides the default routines that the client stub uses to manage memory. The input parameters, $p_allocate$ and p_free specify memory allocator and free routines. The default memory management routines are ISO C malloc() and free() except when the remote call occurs within server code in which case the memory management routines must be rpc ss allocate() and rpc ss free().

The output parameter, status, returns the status code from this routine. This status code indicates whether the routine completed successfully or, if not, why not. Possible status codes and their meanings include:

```
rpc_s_ok
Success.
```

rpc s no memory

Insufficient memory available to set up necessary data structures.

rpc_ss_set_client_alloc_free is the exception-returning version of this function and has no status output parameter. The following exceptions are raised by this routine:

```
rpc x no memory
```

Insufficient memory available to set up necessary data structures.

A thread in a multithreaded application may issue a call to rpc_sm_set_client_alloc_free() or rpc_ss_set_client_alloc_free() while running in any context state, including TPINVALIDCONTEXT.

Return Values None.

```
See Also rpc sm allocate, rpc ss allocate(3c), rpc sm free, rpc ss free(3c)
```

Introduction to the C Language Application-to-Transaction Monitor Interface

rpc_sm_swap_client_alloc_free, rpc_ss_swap_client_alloc_free(3c)

Name

rpc_sm_swap_client_alloc_free(), rpc_ss_swap_client_alloc_free()— Exchanges current memory allocation and freeing mechanism used by client stubs with one supplied by client.

Synopsis

```
#include <rpc/rpc.h>
void rpc_sm_swap_client_alloc_free(
   idl_void_p_t (*p_allocate) (unsigned long size),
   void (*p_free) (idl_void_p_t ptr),
   idl_void_p_t (**p_pold_allocate) (unsigned long size),
   void (**p_pold_free) ( idl_void_p_t ptr),
   unsigned32 *status)

void rpc_ss_swap_client_alloc_free(
   idl_void_p_t (*p_allocate) (unsigned long size),
   void (*p_free) (idl_void_p_t ptr),
   idl_void_p_t (**p_pold_allocate) (unsigned long size),
   void (**p_p pold_free) (idl_void_p_t ptr))
```

Description

The rpc_sm_swap_client_alloc_free() routine exchanges the current allocate and free mechanisms used by the client stubs for routines supplied by the caller. The input parameters, $p_allocate$ and p_free , specify new memory allocation and free routines. The output parameters, $p_pold_allocate$ and p_pold_free return the memory allocation and free routines in use before the call to this routine.

When a callable routine is an RPC client, it may need to ensure which allocate and free routines are used, despite the mechanism its caller had selected. This routine allows scoped replacement of the allocation/free mechanism to allow this.

The output parameter, <code>status</code>, returns the status code from this routine. This status code indicates whether the routine completed successfully or, if not, why not. Possible status codes and their meanings include:

```
rpc_s_ok
Success.

rpc_s_no_memory
Insufficient memory available to set up necessary data structures.
```

rpc_ss_swap_client_alloc_free is the exception-returning version of this function and has no *status* output parameter. The following exceptions are raised by this routine:

```
rpc x no memory
```

Insufficient memory available to set up necessary data structures.

A thread in a multithreaded application may issue a call to

```
rpc_sm_swap_client_alloc_free() or rpc_ss_swap_client_alloc_free()
while running in any context state, including TPINVALIDCONTEXT.
```

Return Values None.

See Also

```
rpc_sm_allocate, rpc_ss_allocate(3c), rpc_sm_free, rpc_ss_free(3c),
rpc sm set client alloc free, rpc ss set client alloc free(3c)
```

setlocale(3c)

Name setlocale()—Modifies and queries a program's locale.

Description

setlocale() selects the appropriate piece of the program's locale as specified by the category and locale arguments. The category argument may have the following values:

LC_CTYPE
LC_NUMERIC
LC_TIME
LC_COLLATE
LC_MONETARY
LC_MESSAGES
LC_ALL

These names are defined in the <code>locale.h</code> header file. For the BEA Tuxedo ATMI system compatibility functions, <code>setlocale()</code> allows only a single <code>locale</code> for all categories. Setting any category is treated the same as <code>LC_ALL</code>, which names the program's entire locale.

A value of "C" for locale specifies the default environment.

A value of "" for locale specifies that the locale should be taken from an environment variable. The environment variable LANG is checked for a locale.

At program startup, the equivalent of

```
setlocale(LC ALL, "C")
```

is executed. This has the effect of initializing each category to the locale described by the environment "C".

If a pointer to a string is given for <code>locale</code>, <code>setlocale()</code> attempts to set the locale for all the categories to <code>locale</code>. The <code>locale</code> must be a simple locale, consisting of a single locale. If <code>setlocale()</code> fails to set the locale for any category, a NULL pointer is returned and the program's locale for all categories is not changed. Otherwise, locale is returned

A NULL pointer for *locale* causes setlocale () to return the current locale associated with the *category*. The program's locale is not changed.

A thread in a multithreaded application may issue a call to setlocale() while running in any context state, including TPINVALIDCONTEXT.

Files \$TUXDIR/locale/C/LANGINFO - time and money database for the C locale \$TUXDIR/locale/10cale/* - locale specific information for each locale \$TUXDIR/locale/C/* CAT - text messages for the C locale

Note A composite locale is not supported. A composite locale is a string beginning with a "/", followed by the locale of each category, separated by a "/".

See Also mklanginfo(1)

ctime(3c), ctype(3c), getdate(3c), localeconv(3c), strftime(3c), strtod(3c), printf(3S), environ(5) in a UNIX system reference manual

setURLEntityCacheDir(3c)

Name setURLEntityCacheDir() - method for setting the directory where the DTD,

schema and Entity files are to be cached.

Synopsis void setURLEntityCacheDir (const char* cachedir)

Description setURLEntityCacheDir() is called when caching is turned on and the caller wants

the DTD, schema and Entity files to be cached to a specific directory. cachedir specifies the absolute path to the location of the files. If this method is not called and caching is turned on either by calling the method <code>setURLEntityCaching()</code> or by not setting the environment variable, then the files are cached in the current directory.

setURLEntityCaching(3c)

Name seturlEntityCaching() - method for setting or unsetting DTD, schema or Entity

file caching for the XML parser.

Synopsis void setURLEntityCaching (bool UseCache)

Description Our enhancement to the Apache Xerces-C++ parser caches the DTD, schema and

Entity files by default. This method allows the caller to turn on or off caching of the files. UseCache is set to false if caching is to be turned off and set to true if caching is

to be turned on.

strerror(3c)

Name strerror()—Gets error message string.

Synopsis #include <string.h>

char *strerror (int errnum);

Description strerror maps the error number in errnum to an error message string, and returns a

pointer to that string. strerror uses the same set of error messages as perror. The

returned string should not be overwritten.

A thread in a multithreaded application may issue a call to strerror() while running

in any context state, including TPINVALIDCONTEXT.

See Also perror(3) in a UNIX system reference manual

strftime(3c)

Name strftime()—Converts date and time to string.

Synopsis #include <time.h>

size_t *strftime (char *s, size_t maxsize, const char *format, const
struct tm *timeptr);

Description

strftime() places characters into the array pointed to by s as controlled by the string pointed to by format. The format string consists of zero or more directives and ordinary characters. All ordinary characters (including the terminating NULL character) are copied unchanged into the array. For strftime(), no more than maxsize characters are placed into the array.

If format is (char *)0, then the locale's default format is used. The default format is the same as "%c".

Each directive is replaced by appropriate characters as described in the following list. The appropriate characters are determined by the LC_TIME category of the program's locale and by the values contained in the structure pointed to by timeptr.

Character	Description
ફેર્ફ	Same as %
%a	Locale's abbreviated weekday name
%A	Locale's full weekday name
%b	Locale's abbreviated month name
%B	Locale's full month name
%C	Locale's appropriate date and time representation
%C	Locale's date and time representation as produced by date(1)
%d	Day of month (01 - 31)
%D	Date as %m/%d/%y
%e	Day of month (1-31; single digits are preceded by a blank)
%h	Locale's abbreviated month name.

%H	Hour (00 - 23)
%I	Hour (01 - 12)
*j	Day number of year (001 - 366)
%m	Month number (01 - 12)
%M	Minute (00 - 59)
%n	Same as \
%p	Locale's equivalent of either AM or PM
%r	Time as %I:%M:%S [AM PM]
%R	Time as %H:%M
%S	Seconds (00 - 61), allows for leap seconds
%t	Insert a tab
%T	Time as %H:%M:%S
%U	Week number of year (00 - 53), Sunday is the first day of week 1
%W	Weekday number ($0 - 6$), Sunday = 0
%W	Week number of year ($00 - 53$), Monday is the first day of week 1
%x	Locale's appropriate date representation
%X	Locale's appropriate time representation
%у	Year within century (00 - 99)
%Y	Year as ccyy (for example, 1986)
%Z	Time zone name or no characters if no time zone exists

The difference between %U and %W lies in which day is counted as the first of the week. Week number 01 is the first week in January starting with a Sunday for %U or a Monday for %W. Week number 00 contains those days before the first Sunday or Monday in January for %U and %W, respectively.

If the total number of resulting characters including the terminating NULL character is not more than <code>maxsize</code>, <code>strftime()</code>, returns the number of characters placed into the array pointed to by <code>s</code> not including the terminating NULL character. Otherwise, zero is returned and the contents of the array are indeterminate.

A thread in a multithreaded application may issue a call to strftime () while running in any context state, including TPINVALIDCONTEXT.

Selecting the Output Language By default, the output of strftime(), appears in U.S. English. The user can request that the output of strftime() be in a specific language by setting the *locale* for *category* LC TIME in setlocale().

Time Zone

The time zone is taken from the environment variable TZ. See ctime(3c) for a description of TZ.

Examples

The example illustrates the use of strftime (). It shows what the string in str would look like if the structure pointed to by tmptr contains the values corresponding to Thursday, August 28, 1986 at 12:44:36 in New Jersey.

strftime (str, strsize, "%A %b %d %j", tmptr)

This results in str containing "Thursday Aug 28 240".

Files

 $\verb§TUXDIR/locale/locale/LANGINFO-- file containing compiled locale-specific date and the state of the containing compiled locale and the state of the containing compiled locale and the state of the containing compiled locale and the containing contai$

and time information

See Also mklanginfo(1), setlocale(3c)

tpabort(3c)

Name tpabort()—Routine for aborting current transaction.

Synopsis #include <atmi.h>

int tpabort(long flags)

Description

tpabort() signifies the abnormal end of a transaction. When this call returns, all changes made to resources during the transaction are undone. Like tpcommit(), this function can be called only by the initiator of a transaction. Participants (that is, service routines) can express their desire to have a transaction aborted by calling tpreturn() with TPFAIL.

If tpabort() is called while call descriptors exist for outstanding replies, then upon return from the function, the transaction is aborted and those descriptors associated with the caller's transaction are no longer valid. Call descriptors not associated with the caller's transaction remain valid.

For each open connection to a conversational server in transaction mode, <code>tpabort()</code> will send a <code>TPEV_DISCONIMM</code> event to the server, whether or not the server has control of a connection. Connections opened before <code>tpbegin()</code> or with the <code>TPNOTRAN</code> flag (that is, not in transaction mode) are not affected.

Currently, the sole argument to the tpabort () function, flags, is reserved for future use and should be set to 0.

In a multithreaded application, a thread in the ${\tt TPINVALIDCONTEXT}$ state is not allowed to issue a call to ${\tt tpabort}$ ().

Return Values

Upon failure, tpabort () returns -1 and sets tperrno to indicate the error condition.

Errors

Upon failure, tpabort () sets tperrno to one of the following values:

[TPEINVAL]

flags is not equal to 0. The caller's transaction is not affected.

[TPEHEURISTIC]

Due to a heuristic decision, the work done on behalf of the transaction was partially committed and partially aborted.

[TPEHAZARD]

Due to some failure, the work done on behalf of the transaction could have been heuristically completed.

[TPEPROTO]

tpabort () was called improperly (for example, by a participant).

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

Notices

When using <code>tpbegin()</code>, <code>tpcommit()</code>, and <code>tpabort()</code> to delineate a BEA Tuxedo ATMI system transaction, it is important to remember that only the work done by a resource manager that meets the XA interface (and is linked to the caller appropriately) has transactional properties. All other operations performed in a transaction are not affected by either <code>tpcommit()</code> or <code>tpabort()</code>.

See Also tpbegin(3c), tpcommit(3c), tpgetlev(3c)

tpacall(3c)

Name tpacall()—Routine for sending a service request.

Synopsis #include <atmi.h>

int tpacall(char *svc, char *data, long len, long flags)

Description

tpacall() sends a request message to the service named by svc. The request is sent out at the priority defined for svc unless overridden by a previous call to tpspri(). If data is non-NULL, it must point to a buffer previously allocated by tpalloc() and len should specify the amount of data in the buffer that should be sent. Note that if data points to a buffer of a type that does not require a length to be specified, (for example, an FML fielded buffer), then len is ignored (and may be 0). If data is NULL, len is ignored and a request is sent with no data portion. The type and subtype of data must match one of the types and subtypes recognized by svc. Note that for each request sent while in transaction mode, a corresponding reply must ultimately be received.

The following is a list of valid flags:

TPNOTRAN

If the caller is in transaction mode and this flag is set, then when svc is invoked, it is not performed on behalf of the caller's transaction. If svc belongs to a server that does not support transactions, then this flag must be set when the caller is in transaction mode. Note that svc may still be invoked in transaction mode but it will not be the same transaction: a svc may have as a configuration attribute that it is automatically invoked in transaction mode. A caller in transaction mode that sets this flag is still subject to the transaction timeout (and no other). If a service fails that was invoked with this flag, the caller's transaction is not affected

TPNOREPLY

Informs tpacall () that a reply is not expected. When TPNOREPLY is set, the function returns 0 on success, where 0 is an invalid descriptor. When the caller is in transaction mode, this setting cannot be used unless TPNOTRAN is also set.

TPNOBLOCK

The request is not sent if a blocking condition exists (for example, the internal buffers into which the message is transferred are full). When TPNOBLOCK is not specified and a blocking condition exists, the caller blocks until the condition subsides or a timeout occurs (either transaction or blocking timeout).

TPNOTIME

This flag signifies that the caller is willing to block indefinitely and wants to be immune to blocking timeouts. Transaction timeouts may still occur.

TPSIGRSTRT

If a signal interrupts any underlying system calls, then the interrupted system call is reissued.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpacall().

Return Values

Upon successful completion, tpacall() returns a descriptor that can be used to receive the reply of the request sent.

Upon failure, tpacall() returns a value of -1 and sets tperrno to indicate the error condition.

Errors

Upon failure, tpacall() sets tperrno to one of the following values. (Unless otherwise noted, failure does not affect the caller's transaction, if one exists.)

[TPEINVAL]

Invalid arguments were given (for example, svc is NULL, data does not point to space allocated with tpalloc(), or flags are invalid).

[TPENOENT]

Cannot send to svc because it does not exist or is a conversational service.

[TPEITYPE]

The type and subtype of data is not one of the allowed types and subtypes that svc accepts.

[TPELIMIT]

The caller's request was not sent because the maximum number of outstanding asynchronous requests has been reached.

[TPETRAN]

 svc belongs to a server that does not support transactions and <code>TPNOTRAN</code> was not set.

[TPETIME]

This error code indicates that either a timeout has occurred or tpacall() has been attempted, in spite of the fact that the current transaction is already marked rollback only.

If the caller is in transaction mode, then either the transaction is already rollback only or a transaction timeout has occurred. The transaction is marked abort-only. If the caller is not in transaction mode, a blocking timeout has occurred. (A blocking timeout cannot occur if TPNOBLOCK and/or TPNOTIME is specified.)

If a transaction timeout has occurred, then, with one exception, any attempts to send new requests or receive outstanding replies will fail with TPETIME until the transaction has been aborted. The exception is a request that does not block, expects no reply, and is not sent on behalf of the caller's transaction (that is, tpacall () with TPNOTRAN, TPNOBLOCK, and TPNOREPLY set).

When a service fails inside a transaction, the transaction is put into the TX ROLLBACK ONLY state. This state is treated, for most purposes, as though it were equivalent to a timeout. All further ATMI calls for this transaction (with the exception of those issued in the circumstances described in the previous paragraph) will fail with TPETIME.

[TPEBLOCK]

A blocking condition exists and TPNOBLOCK was specified.

[TPGOTSIG]

A signal was received and TPSIGRSTRT was not specified.

[TPEPROTO]

tpacall() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred. If a message queue on a remote location is filled, TPEOS may be returned even if tpacall() returned successfully.

```
See Also
```

```
tpalloc(3c), tpcall(3c), tpcancel(3c), tpgetrply(3c), tpgprio(3c),
tpsprio(3c)
```

tpadmcall(3c)

Name tpadmcall()—Administers unbooted application.

Synopsis #include <atmi.h>

#include <fml32.h>
#include <tpadm.h>

int tpadmcall(FBFR32 *inbuf, FBFR32 **outbuf, long flags)

Description

tpadmcall() is used to retrieve and update attributes of an unbooted application. It may also be used in an active application to perform direct retrievals of a limited set of attributes without requiring communication to an external process. This function provides sufficient capability such that complete system configuration and administration can take place through system provided interface routines.

inbuf is a pointer to an FML32 buffer previously allocated with tpalloc() that contains the desired administrative operation and its parameters.

outbuf is the address of a pointer to the FML32 buffer that should contain the results. outbuf must point to an FML32 buffer originally allocated by tpalloc(). If the same buffer is to be used for both sending and receiving, outbuf should be set to the address of inbuf.

Currently, tpadmcall()'s last argument, flags, is reserved for future use and must be set to 0.

MIB(5) should be consulted for generic information on construction of administrative requests. TM_MIB(5) and APPQ_MIB(5) should be consulted for information on the classes that are accessible through tpadmcall().

There are four modes in which calls to tpadmcall() can be made.

Mode 1: Unbooted, Unconfigured Application:

The caller is assumed to be the administrator of the application. The only operations permitted are to SET a NEW T_DOMAIN class object, thus defining an initial configuration for the application, and to GET and SET objects of the classes defined in APPQ_MIB().

Mode 2: Unbooted, Configured Application:

The caller is assigned administrator or other privileges based on a comparison of their UID/GID to that defined in the configuration for the administrator on the local system. The caller may GET and SET any attributes for any class in TM MIB() and APPQ MIB() for which they have the appropriate permissions.

Note that some classes contain only attributes that are inaccessible in an unbooted application and attempts to access these classes will fail.

Mode 3: Booted Application, Unattached Process:

The caller is assigned administrator or other privileges based on a comparison of their UID/GID to that defined in the configuration for the administrator on the local system. The caller may GET any attributes for any class in <code>TM_MIB()</code> for which they have the appropriate permissions. Similarly, the caller may GET and SET any attributes for any class in <code>APPQ_MIB()</code>, subject to class-specific restrictions. Attributes accessible only while ACTIVE will not be returned.

Mode 4: Booted Application, Attached Process:

Permissions are determined from the authentication key assigned at tpinit() time. The caller may GET any attributes for any class in $TM_MIB()$ for which they have the appropriate permissions. Additionally, the caller may GET and SET any attributes for any class in $APPQ_MIB()$, subject to class-specific restrictions.

Access to and update of binary BEA Tuxedo ATMI system application configuration files through this interface routine is controlled through the use of UNIX system permissions on directory names and filenames.

In a multithreaded application, a thread in the ${\tt TPINVALIDCONTEXT}$ state is not allowed to issue a call to ${\tt tpadmcall}$ ().

Environment Variables

The following environment variables must be set prior to calling this routine:

TUXCONFIG

Name of the file or device on which the binary BEA Tuxedo system configuration file for this application is or should be stored.

Notices Use of the TA_OCCURS attribute on GET requests is not supported when using tpadmcall(). GETNEXT requests are not supported when using tpadmcall().

Return Values \quad tpadmcall() returns 0 on success and -1 on failure.

Errors Upon failure, tpadmcall() sets tperrno to one of the following values:

Note: Except for TPEINVAL, the caller's output buffer, <code>outbuf</code>, will be modified to include <code>TA_ERROR</code>, <code>TA_STATUS</code>, and possibly <code>TA_BADFLD</code> attributes to further qualify the error condition. See <code>MIB(5)</code>, <code>TM_MIB(5)</code>, and <code>APPQ_MIB(5)</code> for an explanation of possible error codes returned in this fashion.

[TPEINVAL]

Invalid arguments were specified. The *flags* value is invalid or *inbuf* or *outbuf* are not pointers to typed buffers of type "FML32."

[TPEMIB]

The administrative request failed. outbuf is updated and returned to the caller with FML32 fields indicating the cause of the error as is discussed in MIB(5) and TM MIB(5).

[TPEPROTO]

tpadmcall() was called improperly.

[TPERELEASE]

tpadmcall() was called with the TUXCONFIG environment variable pointing to a different release version configuration file.

[TPEOS]

An operating system error has occurred. A numeric value representing the system call that failed is available in Uunixerr.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to userlog().

Interoperability

This interface supports access and update to the local configuration file and bulletin board only; therefore, there are no interoperability concerns.

Portability

This interface is available only on UNIX system sites running BEA Tuxedo ATMI release 5.0 or later.

Files

```
$\{TUXDIR}/\lib\libtmib.a, \$\{TUXDIR}\/\lib\libqm.a,
$\{TUXDIR}\/\lib\libtmib.so.<rel>, \$\{TUXDIR}\/\lib\/\libqm.so.<rel>,
$\{TUXDIR}\/\lib\/\libtmib.lib, \$\{TUXDIR}\/\lib\/\libqm.lib
```

The libraries must be linked manually when using buildclient. The user must use: -L\${TUXDIR}/lib -ltmid -lqm

See Also

```
ACL_MIB(5), APPQ_MIB(5), EVENT_MIB(5), MIB(5), TM_MIB(5), WS_MIB(5)

Setting Up a BEA Tuxedo Application

Administering a BEA Tuxedo Application at Run Time
```

tpadvertise(3c)

Name tpadvertise()—Routine for advertising a service name.

Synopsis #include <atmi.h>

int tpadvertise(char *svcname, void (*func)(TPSVCINFO *))

Description

tpadvertise() allows a server to advertise the services that it offers. By default, a server's services are advertised when it is booted and unadvertised when it is shutdown

All servers belonging to a Multiple Server, Single Queue (MSSQ) set must offer the same set of services. These routines enforce this rule by affecting the advertisements of all servers sharing an MSSQ set.

tpadvertise() advertises svcname for the server (or the set of servers sharing the caller's MSSQ set). svcname should be 15 characters or less, but cannot be NULL or the NULL string (""). (See *SERVICES section of UBBCONFIG(5).) func is the address of a BEA Tuxedo ATMI system service function. This function will be invoked whenever a request for svcname is received by the server. func cannot be NULL. Explicitly specified function names (see servopts(5)) can be up to 128 characters long. Names longer than 15 characters are accepted and truncated to 15 characters. Users should make sure that truncated names do not match other service names.

If <code>svcname</code> is already advertised for the server and <code>func</code> matches its current function, then <code>tpadvertise()</code> returns success (this includes truncated names that match already advertised names). However, if <code>svcname</code> is already advertised for the server but <code>func</code> does not match its current function, then an error is returned (this can happen if truncated names match already advertised names).

Service names starting with dot (.) are reserved for administrative services. An error will be returned if an application attempts to advertise one of these services.

Return Values

Upon failure, tpadvertise() returns -1 and sets tperrno to indicate the error condition.

Frrors

Upon failure, tpadvertise() sets tperrno to one of the following values:

```
[TPEINVAL]
```

svcname is NULL or the NULL string (""),or begins with a "." or func is NULL.

Introduction to the C Language Application-to-Transaction Monitor Interface

[TPELIMIT]

svcname cannot be advertised because of space limitations. (See MAXSERVICES in the RESOURCES section of UBBCONFIG (5).)

[TPEMATCH]

svcname is already advertised for the server but with a function other than func. Although the function fails, svcname remains advertised with its current function (that is, func does not replace the current function).

[TPEPROTO]

tpadvertise() was called in an improper context (for example, by a client).

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

See Also tpservice(3c), tpunadvertise(3c)

tpalloc(3c)

Name tpalloc()—Routine for allocating typed buffers.

Synopsis #include <atmi.h>

char * tpalloc(char *type, char *subtype, long size)

Description

tpalloc() returns a pointer to a buffer of type type. Depending on the type of buffer, both subtype and size are optional. The BEA Tuxedo ATMI system provides a variety of typed buffers, and applications are free to add their own buffer types. Consult tuxtypes (5) for more details.

If subtype is non-NULL in tmtype_sw for a particular buffer type, then subtype must be specified when tpalloc() is called. The allocated buffer will be at least as large as the larger of size and dfltsize, where dfltsize is the default buffer size specified in tmtype_sw for the particular buffer type. For buffer type STRING the minimum is 512 bytes; for buffer types FML and VIEW the minimum is 1024 bytes.

Note that only the first eight bytes of type and the first 16 bytes of subtype are significant.

Because some buffer types require initialization before they can be used, tpalloc() initializes a buffer (in a BEA Tuxedo ATMI system-specific manner) after it is allocated and before it is returned. Thus, the buffer returned to the caller is ready for use. Note that unless the initialization routine cleared the buffer, the buffer is not initialized to zeros by tpalloc().

A thread in a multithreaded application may issue a call to tpalloc() while running in any context state, including TPINVALIDCONTEXT.

Return Values

Upon successful completion, tpalloc() returns a pointer to a buffer of the appropriate type aligned on a long word; otherwise, it returns NULL and sets tperrno to indicate the condition.

Errors Upon failure, tpalloc() sets tperrno to one of the following values:

[TPEINVAL]

Invalid arguments were given (for example, type is NULL).

[TPENOENT]

No entry in tmtype sw matches type and, if non-NULL, subtype.

[TPEPROTO]

tpalloc() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

Usage If buffer initialization fails, the allocated buffer is freed and tpalloc() fails returning NULL.

This function should not be used in concert with malloc(), realloc(), or free() in the C library (for example, a buffer allocated with tpalloc() should not be freed with free()).

Two buffer types are supported by any compliant implementation of the BEA Tuxedo ATMI system extension. Details are in the Introduction to the C Language Application-to-Transaction Monitor Interface.

See Also tpfree(3c), tprealloc(3c), tptypes(3c)

tpbegin(3c)

Name tpbegin()—Routine for beginning a transaction.

Synopsis #include <atmi.h>

int tpbegin (unsigned long timeout, long flags)

Description

A transaction in the BEA Tuxedo ATMI system is used to define a single logical unit of work that either wholly succeeds or has no effect whatsoever. A transaction allows work being performed in many processes, at possibly different sites, to be treated as an atomic unit of work. The initiator of a transaction uses tpbegin() and either tpcommit() or tpabort() to delineate the operations within a transaction. Once tpbegin() is called, communication with any other program can place the latter (of necessity, a server) in "transaction mode" (that is, the server's work becomes part of the transaction). Programs that join a transaction are called participants. A transaction always has one initiator and can have several participants. Only the initiator of a transaction can call tpcommit() or tpabort(). Participants can influence the outcome of a transaction by the return values (rvals) they use when they call tpreturn(). Once in transaction mode, any service requests made to servers are processed on behalf of the transaction (unless the requester explicitly specifies otherwise).

Note that if a program starts a transaction while it has any open connections that it initiated to conversational servers, these connections will not be upgraded to transaction mode. It is as if the TPNOTRAN flag had been specified on the tpconnect() call.

tpbegin()'s first argument, timeout, specifies that the transaction should be allowed at least timeout seconds before timing out. Once a transaction times out it must be marked abort-only. If timeout is 0, then the transaction is given the maximum number of seconds allowed by the system before timing out (that is, the timeout value equals the maximum value for an unsigned long as defined by the system).

Currently, tpbegin ()'s second argument, flags, is reserved for future use and must be set to 0.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpbegin().

Return Values Upon failure, tpbegin() returns -1 and sets tperrno to indicate the error condition.

Errors Upon failure, tpbegin() sets tperrno to one of the following values:

[TPEINVAL]

flags is not equal to 0.

[TPETRAN]

The caller cannot be placed in transaction mode because an error occurred starting the transaction.

[TPEPROTO]

tpbegin() was called in an improper context (for example, the caller is already in transaction mode).

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

Notices

When using <code>tpbegin()</code>, <code>tpcommit()</code>, and <code>tpabort()</code> to delineate a BEA Tuxedo ATMI system transaction, it is important to remember that only the work done by a resource manager that meets the XA interface (and is linked to the caller appropriately) has transactional properties. All other operations performed in a transaction are not affected by either <code>tpcommit()</code> or <code>tpabort()</code>. See <code>buildserver()</code> for details on linking resource managers that meet the XA interface into a server such that operations performed by that resource manager are part of a BEA Tuxedo ATMI system transaction.

See Also

tpabort(3c), tpcommit(3c), tpgetlev(3c), tpscmt(3c)

tpbroadcast(3c)

Name tpbroadcast ()—Routine to broadcast notification by name.

Synopsis #include <atmi.h>

int tpbroadcast(char *lmid, char *usrname, char *cltname,
 char *data, long len, long flags)

Description

tpbroadcast() allows a client or server to send unsolicited messages to registered clients within the system. The target client set consists of those clients matching identifiers passed to tpbroadcast(). Wildcards can be used in specifying identifiers.

Imid, usrname, and cltname are logical identifiers used to select the target client set. A NULL value for any argument constitutes a wildcard for that argument. A wildcard argument matches all client identifiers for that field. A 0-length string for any argument matches only 0-length client identifiers. Each identifier must meet the size restrictions defined for the system to be considered valid, that is, each identifier must be between 0 and MAXTIDENT characters in length.

The data portion of the request is pointed to by data, a buffer previously allocated by tpalloc(). Len specifies how much of data to send. Note that if data points to a buffer type that does not require a length to be specified (for example, an FML fielded buffer), then Len is ignored (and may be 0). Also, data may be NULL, in which case Len is ignored. The buffer passes through the typed buffer switch routines just as any other outgoing or incoming message would; for example, encode/decode are performed automatically.

The following is a list of valid flags:

TPNOBLOCK

The request is not sent if a blocking condition exists (for example, the internal buffers into which the message is transferred are full).

TPNOTIME

This flag signifies that the caller is willing to block indefinitely and wants to be immune to blocking timeouts. Transaction timeouts may still occur.

TPSIGRSTRT

If a signal interrupts any underlying system calls, then the interrupted system call is reissued. Upon successful return from tpbroadcast(), the message has been delivered to the system for forwarding to the selected clients. tpbroadcast() does not wait for the message to be delivered to each selected client.

Introduction to the C Language Application-to-Transaction Monitor Interface

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpbroadcast().

Return Values

Upon failure, tpbroadcast() returns -1 and sets tperrno to indicate the error condition.

Frrors

Upon failure, tpbroadcast () sends no broadcast messages to application clients and sets tperrno to one of the following values:

[TPEINVAL]

Invalid arguments were given (for example, identifiers too long or invalid flags). Note that use of an illegal LMID will cause tpbroadcast() to fail and return TPEINVAL. However, non-existent user or client names will simply successfully broadcast to no one.

[TPETIME]

A blocking timeout occurred. (A blocking timeout cannot occur if TPNOBLOCK and/or TPNOTIME is specified.)

[TPEBLOCK]

A blocking condition was found on the call and TPNOBLOCK was specified.

[TPGOTSIG]

A signal was received and TPSIGRSTRT was not specified.

[TPEPROTO]

tpbroadcast() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

Portability

The interfaces described in <code>tpnotify(3c)</code> are supported on native site UNIX-based processors. In addition, the routines <code>tpbroadcast()</code> and <code>tpchkunsol()</code> as well as the function <code>tpsetunsol()</code> are supported on UNIX and MS-DOS workstation processors.

Usage

Clients that select signal-based notification may not be signal-able by the system due to signal restrictions. When this occurs, the system generates a log message that it is switching notification for the selected client to dip-in and the client is notified then and thereafter via dip-in notification. (See the description of the RESOURCES NOTIFY parameter in UBBCONFIG() for a detailed discussion of notification methods.)

Because signaling of clients is always done by the system, the behavior of notification is always consistent, regardless of where the originating notification call is made. Therefore to use signal-based notification:

- A native client must be running as an application administrator
- A Workstation client is not required to be running as the application administrator

The ID for the application administrator is identified as part of the configuration for the application.

If signal-based notification is selected for a client, then certain ATMI calls can fail, returning TPGOTSIG due to receipt of an unsolicited message if TPSIGRSTRT is not specified. See UBBCONFIG (5) and tpinit (3c) for more information on notification method selection.

See Also

tpalloc(3c), tpinit(3c), tpnotify(3c), tpterm(3c), UBBCONFIG(5)

tpcall(3c)

Name tpcall()—Routine for sending service request and awaiting its reply.

Description

tpcall() sends a request and synchronously awaits its reply. A call to this function is the same as calling tpacall() immediately followed by tpgetrply(). tpcall() sends a request to the service named by svc. The request is sent out at the priority defined for svc unless overridden by a previous call to tpspri(). The data portion of a request is pointed to by idata, a buffer previously allocated by tpalloc(). ilen specifies how much of idata to send. Note that if idata points to a buffer of a type that does not require a length to be specified, (for example, an FML fielded buffer), then ilen is ignored (and may be 0). Also, idata may be NULL, in which case ilen is ignored. The type and subtype of idata must match one of the types and subtypes recognized by svc.

<code>odata</code> is the address of a pointer to the buffer where a reply is read into, and <code>olen</code> points to the length of that reply. <code>*odata</code> must point to a buffer originally allocated by <code>tpalloc()</code>. If the same buffer is to be used for both sending and receiving, <code>odata</code> should be set to the address of <code>idata</code>. <code>FML</code> and <code>FML32</code> buffers often assume a minimum size of 4096 bytes; if the reply is larger than 4096, the size of the buffer is increased to a size large enough to accommodate the data being returned. Also, if <code>idata</code> and <code>*odata</code> were equal when <code>tpcall()</code> was invoked, and <code>*odata</code> is changed, then <code>idata</code> no longer points to a valid address. Using the old address can lead to data corruption or process exceptions. As of release 6.4, the default allocation for buffers is 1024 bytes. Also, historical information is maintained on recently used buffers, allowing a buffer of optimal size to be reused as a return buffer.

Buffers on the sending side that may be only partially filled (for example, FML or STRING buffers) will have only the amount that is used send. The system may then enlarge the received data size by some arbitrary amount. This means that the receiver may receive a buffer that is smaller than what was originally allocated by the sender, yet larger than the data that was sent.

The receive buffer may grow, or it may shrink, and its address almost invariably changes, as the system swaps buffers around internally. To determine whether (and how much) a reply buffer changed in size, compare its total size before <code>tpgetrply()</code> was issued with * <code>len</code>. See "Introduction to the C Language Application-to-Transaction Monitor Interface" for more information about buffer management.

If *olen is 0 upon return, then the reply has no data portion and neither *odata nor the buffer it points to were modified. It is an error for *odata or olen to be NULL.

The following is a list of valid flags:

TPNOTRAN

If the caller is in transaction mode and this flag is set, then when svc is invoked, it is not performed on behalf of the caller's transaction. Note that svc may still be invoked in transaction mode but it will not be the same transaction: a svc may have as a configuration attribute that it is automatically invoked in transaction mode. A caller in transaction mode that sets this flag is still subject to the transaction timeout (and no other). If a service fails that was invoked with this flag, the caller's transaction is not affected.

TPNOCHANGE

By default, if a buffer is received that differs in type from the buffer pointed to by *odata, then *odata's buffer type changes to the received buffer's type so long as the receiver recognizes the incoming buffer type. When this flag is set, the type of the buffer pointed to by *odata is not allowed to change. That is, the type and subtype of the received buffer must match the type and subtype of the buffer pointed to by *odata.

TPNOBLOCK

The request is not sent if a blocking condition exists (for example, the internal buffers into which the message is transferred are full). Note that this flag applies only to the send portion of tpcall(): the function may block waiting for the reply. When TPNOBLOCK is not specified and a blocking condition exists, the caller blocks until the condition subsides or a timeout occurs (either transaction or blocking timeout).

TPNOTIME

This flag signifies that the caller is willing to block indefinitely and wants to be immune to blocking timeouts. However, if the caller is in transaction mode, this flag has no effect; it is subject to the transaction timeout limit. Transaction timeouts may still occur.

TPSIGRSTRT

If a signal interrupts any underlying system calls, then the interrupted system call is reissued.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpcall().

Introduction to the C Language Application-to-Transaction Monitor Interface

Return Values

Upon successful return from tpcall() or upon return where tperrno is set to TPESVCFAIL, tpurcode() contains an application defined value that was sent as part of tpreturn().

Upon failure, tpcall() returns -1 and sets tperrno to indicate the error condition. If a call fails with a particular tperrno value, a subsequent call to tperrordetail(), with no intermediate ATMI calls, may provide more detailed information about the generated error. Refer to the tperrordetail(3c) reference page for more information.

Errors

Upon failure, tpcall() sets tperrno to one of the following values. (Unless otherwise noted, failure does not affect the caller's transaction, if one exists.)

[TPEINVAL]

Invalid arguments were given (for example, svc is NULL or flags are invalid).

[TPENOENT]

Cannot send to *svc* because it does not exist, or it is a conversational service, or the name provided begins with a dot (.).

[TPEITYPE]

The type and subtype of *idata* is not one of the allowed types and subtypes that *svc* accepts.

[TPEOTYPE]

Either the type and subtype of the reply are not known to the caller; or, TPNOCHANGE was set in flags and the type and subtype of *odata do not match the type and subtype of the reply sent by the service. Neither *odata, its contents, nor *olen is changed. If the service request was made on behalf of the caller's current transaction, then the transaction is marked abort-only since the reply is discarded.

[TPETRAN]

svc belongs to a server that does not support transactions and TPNOTRAN was not set.

[TPETIME]

This error code indicates that either a timeout has occurred or tpcall() has been attempted, in spite of the fact that the current transaction is already marked rollback only.

If the caller is in transaction mode, then either the transaction is already rollback only or a transaction timeout has occurred. The transaction is marked

abort-only. If the caller is not in transaction mode, a blocking timeout has occurred. (A blocking timeout cannot occur if TPNOBLOCK and/or TPNOTIME is specified.) In either case, no changes are made to *odata, its contents, or *olen.

If a transaction timeout has occurred, then, with one exception, any attempts to send new requests or receive outstanding replies will fail with TPETIME until the transaction has been aborted. The exception is a request that does not block, expects no reply, and is not sent on behalf of the caller's transaction (that is, tpacall() with TPNOTRAN, TPNOBLOCK, and TPNOREPLY set).

When a service fails inside a transaction, the transaction is put into the TX_ROLLBACK_ONLY state. This state is treated, for most purposes, as though it were equivalent to a timeout. All further ATMI calls for this transaction (with the exception of those issued in the circumstances described in the previous paragraph) will fail with TPETIME.

[TPESVCFAIL]

The service routine sending the caller's reply called tpreturn() with TPFAIL. This is an application-level failure. The contents of the service's reply, if one was sent, is available in the buffer pointed to by *odata. If the service request was made on behalf of the caller's current transaction, then the transaction is marked abort-only. Note that regardless of whether the transaction has timed out, the only valid communications before the transaction is aborted are calls to tpacall() with TPNOREPLY, TPNOTRAN, and TPNOBLOCK set.

[TPESVCERR]

A service routine encountered an error either in tpreturn (3c) or tpforward (3c) (for example, bad arguments were passed). No reply data is returned when this error occurs (that is, neither *odata, its contents, nor *olen is changed). If the service request was made on behalf of the caller's transaction (that is, TPNOTRAN was not set), then the transaction is marked abort-only. Note that regardless of whether the transaction has timed out, the only valid communications before the transaction is aborted are calls to tpacall() with TPNOREPLY, TPNOTRAN, and TPNOBLOCK set. If either SVCTIMEOUT in the UBBCONFIG file or TA_SVCTIMEOUT in the TM_MIB is non-zero, TPESVCERR is returned when a service timeout occurs.

[TPEBLOCK]

A blocking condition was found on the send call and TPNOBLOCK was specified.

Introduction to the C Language Application-to-Transaction Monitor Interface

[TPGOTSIG]

A signal was received and TPSIGRSTRT was not specified.

[TPEPROTO]

tpcall() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred. If a message queue on a remote location is filled, TPEOS may be returned even if tpcall() returned successfully.

See Also

tpacall(3c),tpalloc(3c),tperrordetail(3c),tpforward(3c),tpfree(3c),
tpgprio(3c),tprealloc(3c),tpreturn(3c),tpsprio(3c),
tpstrerrordetail(3c),tptypes(3c)

tpcancel(3c)

Name tpcancel()—Routine for canceling a call descriptor for outstanding reply.

Synopsis #include <atmi.h>
 int tpcancel(int cd)

Description tpcancel() cancels a call descriptor, cd, returned by tpacall(). It is an error to

attempt to cancel a call descriptor associated with a transaction.

Upon success, cd is no longer valid and any reply received on behalf of cd will be silently discarded.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpcancel().

Return Values Upon failure, tpcancel () returns -1 and sets tperrno to indicate the error condition.

Errors Upon failure, tpcancel() sets tperrno to one of the following values:

[TPEBADDESC]

cd is an invalid descriptor.

[TPETRAN]

cd() is associated with the caller's transaction. cd remains valid and the caller's current transaction is not affected.

[TPEPROTO]

tpcancel() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

See Also tpacall(3c)

tpchkauth(3c)

Name tpchkauth()—Routine for checking if authentication required to join an application.

Synopsis #include <atmi.h>

int tpchkauth(void)

Description tpchkauth() checks if authentication is required by the application configuration.

This is typically used by application clients prior to calling tpinit() to determine if

a password should be obtained from the user.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed

to issue a call to tpchkauth().

Return Values Upon success, tpchkauth() returns one of the following non-negative values:

TPNOAUTH

Indicates that no authentication is required.

TPSYSAUTH

Indicates that system authentication only is required.

TPAPPAUTH

Indicates that both system and application specific authentication are required.

Upon failure, tpchkauth() returns -1 and sets tperrno to indicate the error condition.

Errors Upon failure, tpchkauth() sets tperrno to one of the following values:

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

Interoperability tpchkauth () is available only on sites running release 4.2 or later.

Section 3c - C Functions

Portability The interfaces described in tpchkauth(3c) are supported on UNIX, Windows, and

MS-DOS operating systems.

See Also tpinit(3c)

tpchkunsol(3c)

Name tpchkunsol()—Routine for checking for unsolicited message.

Synopsis #include <atmi.h>
 int tpchkunsol(void)

Description tpchkunsol () is used by a client to trigger checking for unsolicited messages. Calls to this routine in a client using signal-based notification do nothing and return immediately. This call has no arguments. Calls to this routine can result in calls to an

application-defined unsolicited message handling routine by the BEA Tuxedo ATMI system libraries.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed

to issue a call to tpchkunsol().

Return Values Upon successful completion, tpchkunsol() returns the number of unsolicited messages dispatched; otherwise it returns -1 and sets tperrno to indicate the error

condition.

Errors Upon failure, tpchkunsol() sets tperrno to one of the following values:

[TPEPROTO]

tpchkunsol () was called in an improper context (for example, from within a server).

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

Portability

The interfaces described in tpnotify (3c) are supported on native site UNIX-based processors. In addition, the routines tpbroadcast() and tpchkunsol() as well as the function tpsetunsol() are supported on UNIX and MS-DOS workstation processors.

Clients that select signal-based notification may not be signal-able by the system due to signal restrictions. When this occurs, the system generates a log message that it is switching notification for the selected client to dip-in and the client is notified then and thereafter via dip-in notification. (See the description of the RESOURCES NOTIFY parameter in UBBCONFIG (5) for a detailed discussion of notification methods.)

Because signaling of clients is always done by the system, the behavior of notification is always consistent, regardless of where the originating notification call is made. Therefore to use signal-based notification:

- A native client must be running as an application administrator
- A Workstation client is not required to be running as the application administrator

The ID for the application administrator is identified as part of the configuration for the application.

If signal-based notification is selected for a client, then certain ATMI calls can fail, returning <code>TPGOTSIG</code> due to receipt of an unsolicited message if <code>TPSIGRSTRT</code> is not specified. See <code>UBBCONFIG(5)</code> and <code>tpinit(3c)</code> for more information on notification method selection.

See Also tpbroadcast(3c),tpinit(3c), tpnotify(3c), tpsetunsol(3c)

tpclose(3c)

Name tpclose()—Routine for closing a resource manager.

Synopsis #include <atmi.h>
 int tpclose(void)

Description

tpclose() tears down the association between the caller and the resource manager to which it is linked. Since resource managers differ in their close semantics, the specific information needed to close a particular resource manager is placed in a configuration file.

If a resource manager is already closed (that is, tpclose() is called more than once), no action is taken and success is returned.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpclose().

Return Values

Upon failure, tpclose() returns -1 and sets tperrno to indicate the error condition.

Errors

Upon failure, tpclose() fails and sets tperrno to one of the following values:

[TPERMERR]

A resource manager failed to close correctly. More information concerning the reason a resource manager failed to close can be obtained by interrogating a resource manager in its own specific manner. Note that any calls to determine the exact nature of the error hinder portability.

[TPEPROTO]

tpclose() was called in an improper context (for example, while the caller is in transaction mode).

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

See Also tpopen (3c)

tpcommit(3c)

Name tpcommit()—Routine for committing current transaction.

Synopsis #include <atmi.h>

int tpcommit(long flags)

Description

tpcommit() signifies the end of a transaction, using a two-phase commit protocol to coordinate participants. tpcommit() can be called only by the initiator of a transaction. If any of the participants cannot commit the transaction (for example, they call tpreturn() with TPFAIL), then the entire transaction is aborted and tpcommit() fails. That is, all of the work involved in the transaction is undone. If all participants agree to commit their portion of the transaction, then this decision is logged to stable storage and all participants are asked to commit their work.

Depending on the setting of the TP_COMMIT_CONTROL characteristic (see tpscmt(3c)), tpcommit() can return successfully either after the commit decision has been logged or after the two-phase commit protocol has completed. If tpcommit() returns after the commit decision has been logged but before the second phase has completed (TP_CMT_LOGGED), then all participants have agreed to commit the work they did on behalf of the transaction and should fulfill their promise to commit the transaction during the second phase. However, because tpcommit() is returning before the second phase has completed, there is a hazard that one or more of the participants can heuristically complete their portion of the transaction (in a manner that is not consistent with the commit decision) even though the function has returned success.

If the TP_COMMIT_CONTROL characteristic is set such that tpcommit() returns after the two-phase commit protocol has completed (TP_CMT_COMPLETE), then its return value reflects the exact status of the transaction (that is, whether the transaction heuristically completed or not).

Note that if only a single resource manager is involved in a transaction, then a one-phase commit is performed (that is, the resource manager is not asked whether or not it can commit; it is simply told to commit). In this case, the <code>TP_COMMIT_CONTROL</code> characteristic has no bearing and <code>tpcommit()</code> will return heuristic outcomes if present.

If tpcommit() is called while call descriptors exist for outstanding replies, then upon return from the function, the transaction is aborted and those descriptors associated with the caller's transaction are no longer valid. Call descriptors not associated with the caller's transaction remain valid.

tpcommit() must be called after all connections associated with the caller's transaction are closed (otherwise TPEABORT is returned, the transaction is aborted and these connections are disconnected in a disorderly fashion with a TPEV_DISCONIMM event). Connections opened before tpbegin() or with the TPNOTRAN flag (that is, connections not in transaction mode) are not affected by calls to tpcommit() or tpabort().

Currently, tpcommit ()'s sole argument, flags, is reserved for future use and must be set to 0.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpcommit().

Return Values

Upon failure, tpcommit () returns -1 and sets tperrno to indicate the error condition.

Errors

Upon failure, tpcommit() sets tperrno to one of the following values:

[TPEABORT]

The transaction could not commit because either the work performed by the initiator or by one or more of its participants could not commit. This error is also returned if tpcommit() is called with outstanding replies or open conversational connections.

[TPEHAZARD]

Due to some failure, the work done on behalf of the transaction could have been heuristically completed.

[TPEHEURISTIC]

Due to a heuristic decision, the work done on behalf of the transaction was partially committed and partially aborted.

[TPEINVAL]

flags is not equal to 0. The caller's transaction is not affected.

[TPEOS]

An operating system error has occurred.

[TPEPROTO]

tpcommit() was called in an improper context (for example, by a participant).

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPETIME]

The transaction has timed out and its status is unknown: it may have been either committed or aborted. If a transaction has timed out and its status is known to be aborted, then TPEABORT is returned.

Notices

When using <code>tpbegin()</code>, <code>tpcommit()</code>, and <code>tpabort()</code> to delineate a BEA Tuxedo ATMI system transaction, it is important to remember that only the work done by a resource manager that meets the XA interface (and is linked to the caller appropriately) has transactional properties. All other operations performed in a transaction are not affected by either <code>tpcommit()</code> or <code>tpabort()</code>. See <code>buildserver(1)</code> for details on linking resource managers that meet the XA interface into a server such that operations performed by that resource manager are part of a BEA Tuxedo ATMI system transaction.

See Also

tpabort(3c), tpbegin(3c), tpconnect(3c), tpgetlev(3c), tpreturn(3c),
tpscmt(3c)

tpconnect(3c)

Name tpconnect()—Routine for establishing a conversational service connection.

Synopsis #include <atmi.h>

int tpconnect(char *svc, char *data, long len, long flags)

Description

tpconnect () allows a program to set up a half-duplex connection to a conversational service, *svc*. The name must be one of the conversational service names posted by a conversational server.

As part of setting up a connection, the caller can pass application-defined data to the listening program. If the caller chooses to pass data, then <code>data</code> must point to a buffer previously allocated by <code>tpalloc()</code>. <code>len</code> specifies how much of the buffer to send. Note that if <code>data</code> points to a buffer of a type that does not require a length to be specified, (for example, an <code>FML</code> fielded buffer), then <code>len</code> is ignored (and may be 0). Also, <code>data</code> can be NULL in which case <code>len</code> is ignored (no application data is passed to the conversational service). The type and subtype of <code>data</code> must match one of the types and subtypes recognized by <code>svc. data</code> and <code>len</code> are passed to the conversational service via the <code>TPSVCINFO</code> structure with which the service is invoked; the service does not have to call <code>tprecv()</code> to get the data.

The following is a list of valid flags:

TPNOTRAN

If the caller is in transaction mode and this flag is set, then when svc is invoked, it is not performed on behalf of the caller's transaction. Note that svc may still be invoked in transaction mode but it will not be the same transaction: a svc may have as a configuration attribute that it is automatically invoked in transaction mode. A caller in transaction mode that sets this flag is still subject to the transaction timeout (and no other). If a service fails that was invoked with this flag, the caller's transaction is not affected.

TPSENDONLY

The caller wants the connection to be set up initially such that it can only send data and the called service can only receive data (that is, the caller initially has control of the connection). Either TPSENDONLY or TPRECVONLY must be specified.

TPRECVONLY

The caller wants the connection to be set up initially such that it can only receive data and the called service can only send data (that is, the service being called initially has control of the connection). Either TPSENDONLY or TPRECVONLY must be specified.

TPNOBLOCK

The connection is not established and the data is not sent if a blocking condition exists (for example, the data buffers through which the message is sent are full). Note that this flag applies only to the send portion of tpconnect(); the function may block waiting for an acknowledgement from the server. When TPNOBLOCK is not specified and a blocking condition exists, the caller blocks until the condition subsides or a blocking timeout or transaction timeout occurs.

TPNOTIME

This flag signifies that the caller is willing to block indefinitely and wants to be immune to blocking timeouts. Transaction timeouts will still affect the program.

TPSIGRSTRT

If a signal interrupts any underlying system calls, then the interrupted call is reissued.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpconnect().

Return Values

Upon successful completion, tpconnect() returns a descriptor that is used to refer to the connection in subsequent calls. Otherwise it returns -1 and sets tperrno to indicate the error condition

Errors

Upon failure, tpconnect() sets tperrno to one of the following values. (Unless otherwise noted, failure does not affect the caller's transaction, if one exists.)

[TPEBLOCK]

A blocking condition exists and TPNOBLOCK was specified.

[TPEINVAL]

Invalid arguments were given (for example, svc is NULL, data is non-NULL and does not point to a buffer allocated by tpalloc(), TPSENDONLY or TPRECVONLY was not specified in flags, or flags are otherwise invalid).

[TPEITYPE]

The type and subtype of data is not one of the allowed types and subtypes that svc accepts.

[TPELIMIT]

The caller's request was not sent because the maximum number of outstanding connections has been reached.

[TPENOENT]

Cannot initiate a connection to svc because it does not exist or is not a conversational service.

[TPEOS]

An operating system error has occurred.

[TPEPROTO]

tpconnect() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPETIME]

This error code indicates that either a timeout has occurred or tpconnect() has been attempted, in spite of the fact that the current transaction is already marked rollback only.

If the caller is in transaction mode, then either the transaction is already rollback only or a transaction timeout has occurred. The transaction is marked abort-only. If the caller is not in transaction mode, a blocking timeout has occurred. (A blocking timeout cannot occur if TPNOBLOCK and/or TPNOTIME is specified.)

If a transaction timeout has occurred, then, with one exception, any attempts to start new conversations, send new requests, or receive outstanding replies will fail with TPETIME until the transaction has been aborted. The exception is a request that does not block, expects no reply, and is not sent on behalf of the caller's transaction (that is, tpacall() with TPNOTRAN, TPNOBLOCK, and TPNOREPLY set).

When a service fails inside a transaction, the transaction is put into the TX_ROLLBACK_ONLY state. This state is treated, for most purposes, as though it were equivalent to a timeout. All further ATMI calls for this transaction

(with the exception of those issued in the circumstances described in the previous paragraph) will fail with TPETIME.

[TPETRAN]

 ${\it svc}$ belongs to a program that does not support transactions and <code>TPNOTRAN</code> was not set.

[TPGOTSIG]

A signal was received and TPSIGRSTRT was not specified.

See Also tpalloc(3c),tpdiscon(3c), tprecv(3c), tpsend(3c), tpservice(3c)

tpconvert(3c)

Name tpconvert ()—Converts structures to/from string representations.

Synopsis #include <atmi.h>
#include <xa.h>

int tpconvert(char *strrep, char *binrep, long flags)

Description

tpconvert () converts the string representation of interface structures (*strrep*) to or from the binary representation (*binrep*).

Both the direction of the conversion and the interface structure type are determined from the flags argument. To convert a structure from binary representation to string representation, the programmer must set the TPTOSTRING bit in flags. To convert a structure from string to binary the programmer must clear the bit. The following flags are defined to indicate the particular structure type to be converted; only one may be specified at a time:

TPCONVCLTID

Convert CLIENTID (see atmi.h).

TPCONVTRANID

Convert TPTRANID (see atmi.h).

TPCONVXID

Convert XID (see xa.h).

For conversions from binary to string representation, *strrep* should be at least TPCONVMAXSTR characters in length.

Note that unequal string versions of TPTRANID and XID values may be considered equal by the system when accessing TM_MIB (5) classes that allow these values as key fields (for example, T_TRANSACTION or T_ULOG). Therefore, string values for these data types should not be fabricated or manipulated by application programs. TM_MIB (5) guarantees that only objects matching the global transaction identified by the string are returned when one of these values is used as a key field.

A thread in a multithreaded application may issue a call to tpconvert() while running in any context state, including TPINVALIDCONTEXT.

Return Values

Upon failure, tpconvert() returns -1 and sets tperrno to indicate the error condition.

Errors Under the following conditions, tpconvert() fails and sets tperrno to one of the following values:

[TPEINVAL]

Invalid arguments were specified. strrep or binrep is a NULL pointer, or flags does not indicate exactly one structure type.

[TPEOS]

An operating system error has occurred. A numeric value representing the system call that failed is available in Uunixerr.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to userlog(3c).

Portability This interface is available only on BEA Tuxedo ATMI release 5.0 or later. This interface is available on workstation platforms.

See Also tpresume (3c), tpservice (3c), tpsuspend (3c), tx info (3c), TM MIB (5)

tpconvmb(3c)

Name

tpconvmb()—Converts encoding of characters in an input buffer to a named target encoding.

Synopsis

```
#include <atmi.h>
extern int tperrno;
int
tpconvmb (char **bufp, int *len, char *target encoding, long flags)
```

Description

This function is used to convert an input buffer to a desired codeset encoding.

This fuction is added for user convenience and is not required for normal codeset data conversion that is done automatically.

The bufp argument is a valid pointer to an MBSTRING typed buffer message. This pointer will be reallocated internally if the size of the buffer is insufficient to handle the output data of the converted buffer.

The *len* argument, on input, contains the number of bytes that need to be converted. Upon successful completion of conversion it will contain the number of bytes used in bufp.

The target_encoding argument is the target codeset encoding name used to convert the typed buffer provided in the bufp message.

The *flags* argument is not used by the Tuxedo conversion code. It will be passed along to the buffer type switch function for user defined conversion functions.

Return Values

Upon success, tpconvmb() returns 0. This function returns -1 on error and sets tperrno as described below. The function may fail for the following reasons.

[TPEINVAL]

```
target_encoding, len, or bufp arguments are NULL. len or target_encoding is invalid.
```

[TPEPROTO]

bufp translates to a Tuxedo buffer that does not have a buffer typeswitch conversion function

[TPESYSTEM]

A Tuxedo system error has occurred. (e.g. bufp does not correspond to a valid Tuxedo buffer).

[TPEOS]

An operating system error has occurred. A numeric value representing the system call that failed is available in Uunixerr.

See Also tpalloc(3c), tpgetmbenc(3c), tpsetmbenc(3c)

tpcryptpw(3c)

Name tpcryptpw()—Encrypts the application password in an administrative request.

Synopsis #include <atmi.h>
#include <fml32.h>

int tpcryptpw(FBFR32 *buf)

Description

tpcryptpw() is used to encrypt the application password stored in an administrative request buffer prior to sending the request for servicing. Application passwords are stored as string values using the FML32 field identifier TA_PASSWORD. This encryption is necessary to insure that clear text passwords are not compromised and that appropriate propagation of the update can take place to all active application sites. Additional system fields may be added to the callers buffer and existing fields may be modified to satisfy the request.

A thread in a multithreaded application may issue a call to tpcryptpw() while running in any context state, including TPINVALIDCONTEXT.

Return Values

Upon failure, tpcryptpw() returns -1 and sets tperrno to indicate the error condition.

Errors

Upon failure, tpcryptpw() sets tperrno to one of the following values:

[TPEINVAL]

Invalid arguments were specified. The buf value is NULL, does not point to a FML32 typed buffer or appdir could not be determined from the input buffer or the environment.

[TPEPERM]

The calling process did not have the appropriate permissions necessary to perform the requested task.

[TPEOS]

An operating system error has occurred. A numeric value representing the system call that failed is available in Uunixerr.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to userlog(3c).

Portability

This interface is available only on UNIX system sites running BEA Tuxedo ATMI release 5.0 or later. This interface is not available to Workstation clients.

Files \${TUXDIR}/lib/libtmib.a, \${TUXDIR}/lib/libtmib.so.rel

See Also MIB(5), TM MIB(5)

Setting Up a BEA Tuxedo Application

Administering a BEA Tuxedo Application at Run Time

tpdequeue(3c)

Name tpdequeue ()—Routine to dequeue a message from a queue.

Synopsis #include <atmi.h>

int tpdequeue(char *qspace, char *qname, TPQCTL *ctl, char **data,
long *len, long flags)

Description

tpdequeue () takes a message for processing from the queue named by *qname* in the *qspace* queue space.

By default, the message at the top of the queue is dequeued. The order of messages on the queue is defined when the queue is created. The application can request a particular message for dequeuing by specifying its message identifier or correlation identifier using the ctl parameter. ctl flags can also be used to indicate that the application wants to wait for a message, in the case when a message is not currently available. It is possible to use the ctl parameter to look at a message without removing it from the queue or changing its relative position on the queue. See the section below describing this parameter.

data is the address of a pointer to the buffer into which a message is read, and len points to the length of that message. *data must point to a buffer originally allocated by tpalloc(). If a message is larger than the buffer passed to tpdequeue, the buffer is increased in size to accommodate the message. To determine whether a message buffer changed in size, compare its (total) size before tpdequeue() was issued with *len. If *len is larger, then the buffer has grown; otherwise, the buffer has not changed size. Note that *data may change for reasons other than the buffer's size increased. If *len is 0 upon return, then the message dequeued has no data portion and neither *data nor the buffer it points to were modified. It is an error for *data or len to be NULL.

The message is dequeued in transaction mode if the caller is in transaction mode and the TPNOTRAN flag is not set. This has the effect that if tpdequeue() returns successfully and the caller's transaction is committed successfully, then the message is removed from the queue. If the caller's transaction is rolled back either explicitly or as the result of a transaction timeout or some communication error, then the message will be left on the queue (that is, the removal of the message from the queue is also rolled back). It is not possible to enqueue and dequeue the same message within the same transaction.

The message is not dequeued in transaction mode if either the caller is not in transaction mode, or the TPNOTRAN flag is set. When not in transaction mode, if a communication error or a timeout occurs, the application will not know whether or not the message was successfully dequeued and the message may be lost.

The following is a list of valid flags:

TPNOTRAN

If the caller is in transaction mode and this flag is set, the message is not dequeued within the caller's transaction. A caller in transaction mode that sets this flag is still subject to the transaction timeout (and no other) when dequeuing the message. If message dequeuing fails, the caller's transaction is not affected.

TPNOBLOCK

The message is not dequeued if a blocking condition exists. If this flag is set and a blocking condition exists such as the internal buffers into which the message is transferred are full, the call fails and tperrno is set to TPEBLOCK. If this flag is set and a blocking condition exists because the target queue is opened *exclusively* by another application, the call fails, tperrno is set to TPEDIAGNOSTIC, and the diagnostic field of the TPQCTL structure is set to QMESHARE. In the latter case, the other application, which is based on a BEA product other than the BEA Tuxedo ATMI system, opened the queue for exclusive read and/or write using the Queuing Services API (QSAPI).

When TPNOBLOCK is not set and a blocking condition exists, the caller blocks until the condition subsides or a timeout occurs (either transaction or blocking timeout). This blocking condition does not include blocking on the queue itself if the TPQWAIT option in flags (of the TPQCTL structure) is specified.

TPNOTIME

Setting this flag signifies that the caller is willing to block indefinitely and wants to be immune to blocking timeouts. Transaction timeouts may still occur

TPNOCHANGE

When this flag is set, the type of the buffer pointed to by *data is not allowed to change. By default, if a buffer is received that differs in type from the buffer pointed to by *data, then *data's buffer type changes to the received buffer's type so long as the receiver recognizes the incoming buffer type. That is, the type and subtype of the dequeued message must match the type and subtype of the buffer pointed to by *data.

TPSTGRSTRT

Setting this flag indicates that any underlying system calls that are interrupted by a signal should be reissued. When this flag is not set and a signal interrupts a system call, the call fails and sets tperrno to TPGOTSIG.

If tpdequeue () returns successfully, the application can retrieve additional information about the message using the ctl data structure. The information may include the message identifier for the dequeued message; a correlation identifier that should accompany any reply or failure message so that the originator can correlate the message with the original request; the quality of service the message was delivered with, the quality of service any replies to the message should be delivered with; the name of a reply queue if a reply is desired; and the name of the failure queue on which the application can queue information regarding failure to dequeue the message. These are described below.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpdequeue().

Control Parameter

The TPQCTL structure is used by the application program to pass and retrieve parameters associated with dequeuing the message. The *flags* element of TPQCTL is used to indicate what other elements in the structure are valid.

On input to tpdequeue (), the following elements may be set in the TPQCTL structure:

The following is a list of valid bits for the flags parameter controlling input information for tpdequeue():

TPNOFLAGS

No flags are set. No information is taken from the control structure.

TPOGETBYMSGID

Setting this flag requests that the message with the message identifier specified by ctl->msgid be dequeued. The message identifier may be acquired by a prior call to tpenqueue(3c). Note that a message identifier changes if the message has moved from one queue to another. Note also that the entire 32 bytes of the message identifier value are significant, so the value specified by ctl->msgid must be completely initialized (for example, padded with NULL characters).

TPOGETBYCORRID

Setting this flag requests that the message with the correlation identifier specified by ctl->corrid be dequeued. The correlation identifier is specified by the application when enqueuing the message with tpenqueue(). Note that the entire 32 bytes of the correlation identifier value are significant, so the value specified by ctl->corrid must be completely initialized (for example, padded with NULL characters).

TPQWAIT

Setting this flag indicates that an error should not be returned if the queue is empty. Instead, the process should wait until a message is available. If TPQWAIT is set in conjunction with TPQGETBYMSGID or TPQGETBYCORRID, it indicates that an error should not be returned if no message with the specified message identifier or correlation identifier is present in the queue. Instead, the process should wait until a message meeting the criteria is available. The process is still subject to the caller's transaction timeout, or, when not in transaction mode, the process is subject to the timeout specified on the TMQUEUE process by the -t option.

If a message matching the desired criteria is not immediately available and the configured action resources are exhausted, tpdequeue returns -1, tperrno is set to TPEDIAGNOSTIC, and the diagnostic field of the TPQCTL structure is set to QMESYSTEM.

Note that each <code>tpdequeue()</code> request specifying the <code>TPQWAIT</code> control parameter requires that a queue manager (<code>TMQUEUE</code>) action object be available if a message satisfying the condition is not immediately available. If an action object is not available, the <code>tpdequeue()</code> request fails. The number of available queue manager actions are specified when a queue space is created or modified. When a waiting dequeue request completes, the associated action object associated is made available for another request.

TPQPEEK

If this flag is set, the specified message is read but is not removed from the queue. This flag implies the TPNOTRAN flag has been set for the tpdequeue() operation. That is, non-destructive dequeuing is non-transactional. Note that it is not possible to read messages enqueued or dequeued within a transaction before the transaction completes.

When a thread is non-destructively dequeuing a message using TPQPEEK, the message may not be seen by other non-blocking dequeuers for the brief time the system is processing the non-destructive dequeue request. This includes

dequeuers using specific selection criteria (such as message identifier and correlation identifier) that are looking for the message currently being non-destructively dequeued.

On output from tpdequeue(), the following elements may be set in the TPQCTL structure:

The following is a list of valid bits for the flags parameter controlling output information from tpdequeue(). For any of these bits, if the flag bit is turned on when tpdequeue() is called, the associated element in the structure is populated with the value provided when the message was queued, and the bit remains set. If a value is not available (that is, no value was provided when the message was queued) or the bit is not set when tpdequeue() is called, tpdequeue() completes with the flag turned off.

TPOPRIORITY

If this flag is set, the call to tpdequeue() is successful, and the message was queued with an explicit priority, then the priority is stored in ctl->priority. The priority is in the range 1 to 100, inclusive, and the higher the number, the higher the priority (that is, a message with a higher number is dequeued before a message with a lower number). For queues not ordered by priority, the value is informational.

If no priority was explicitly specified when the message was queued and the call to tpdequeue() is successful, the priority for the message is 50.

TPQMSGID

If this flag is set and the call to tpdequeue() is successful, the message identifier is stored in ctl->msgid. The entire 32 bytes of the message identifier value are significant.

TPOCORRID

If this flag is set, the call to tpdequeue() is successful, and the message was queued with a correlation identifier, then the correlation identifier is stored in ctl->corrid. The entire 32 bytes of the correlation identifier value are significant. Any BEA Tuxedo ATMI/Q provided reply to a message has the correlation identifier of the original request message.

TPQDELIVERYQOS

If this flag is set, the call to tpdequeue() is successful, and the message was queued with a delivery quality of service, then the flag—

TPQQOSDEFAULTPERSIST, TPQQOSPERSISTENT, or

TPQQOSNONPERSISTENT—is stored in ct1->delivery_qos. If no delivery quality of service was explicitly specified when the message was queued, the default delivery policy of the target queue dictates the delivery quality of service for the message.

TPOREPLYOOS

If this flag is set, the call to tpdequeue() is successful, and the message was queued with a reply quality of service, then the flag—

TPQQOSDEFAULTPERSIST, TPQQOSPERSISTENT, or

TPQQOSNONPERSISTENT—is stored in ct1->rep1y_qos. If no reply quality of service was explicitly specified when the message was queued, the default delivery policy of the ct1->rep1yqueue queue dictates the delivery quality of service for any reply.

Note that the default delivery policy is determined when the reply to a message is enqueued. That is, if the default delivery policy of the reply queue is modified between the time that the original message is enqueued and the reply to the message is enqueued, the policy used is the one in effect when the reply is finally enqueued.

TPQREPLYQ

If this flag is set, the call to tpdequeue() is successful, and the message was queued with a reply queue, then the name of the reply queue is stored in ctl->replyqueue. Any reply to the message should go to the named reply queue within the same queue space as the request message.

TPOFAILUREO

If this flag is set, the call to tpdequeue() is successful, and the message was queued with a failure queue, then the name of the failure queue is stored in ctl->failurequeue. Any failure message should go to the named failure queue within the same queue space as the request message.

The following remaining bits for the *flags* parameter are cleared (set to zero) when tpdequeue() is called: TPQTOP, TPQBEFOREMSGID, TPQTIME_ABS, TPQTIME_REL, TPQEXPTIME_ABS, TPQEXPTIME_REL, and TPQEXPTIME_NONE. These bits are valid bits for the *flags* parameter controlling input information for tpenqueue().

If the call to tpdequeue() failed and tperrno is set to TPEDIAGNOSTIC, a value indicating the reason for failure is returned in ctl—>diagnostic. The possible values are defined below in the Diagnostics section.

Additionally on output, if the call to tpdequeue() is successful, $ctl \rightarrow appkey$ is set to the application authentication key, $ctl \rightarrow cltid$ is set to the identifier for the client originating the request, and $ctl \rightarrow urcode$ is set to the user-return code value that was set when the message was enqueued.

If the ct1 parameter is NULL, the input flags are considered to be TPNOFLAGS, and no output information is made available to the application program.

Return Values

Upon failure, tpdequeue () returns -1 and sets tperrno to indicate the error condition.

Errors

Upon failure, tpdequeue() sets tperrno to one of the following values. (Unless otherwise noted, failure does not affect the caller's transaction, if one exists.)

[TPEINVAL]

Invalid arguments were given (for example, *qname* is NULL, *data* does not point to space allocated with tpalloc() or *flags* are invalid).

[TPENOENT]

Cannot access the *qspace* because it is not available (that is, the associated TMQUEUE (5) server is not available), or cannot start a global transaction due to the lack of entries in the Global Transaction Table (GTT).

[TPEOTYPE]

Either the type and subtype of the dequeued message are not known to the caller; or, TPNOCHANGE was set in flags and the type and subtype of *data do not match the type and subtype of the dequeued message. In either case, *data, its contents, and *len are not changed. When the call is made in

transaction mode and this error occurs, the transaction is marked abort-only, and the message remains on the queue.

[TPETIME]

This error code indicates that either a timeout has occurred or tpdequeue() has been attempted, in spite of the fact that the current transaction is already marked rollback only.

If the caller is in transaction mode, then either the transaction is already rollback only or a transaction timeout has occurred. The transaction is marked abort-only. If the caller is not in transaction mode, a blocking timeout has occurred. (A blocking timeout cannot occur if TPNOBLOCK and/or TPNOTIME is specified.) In either case, no changes are made to *data, its contents, or *len.

If a transaction timeout has occurred, then, with one exception, any attempts to perform further conversational work, send new requests, or receive outstanding replies will fail with TPETIME until the transaction has been aborted. The exception is a request that does not block, expects no reply, and is not sent on behalf of the caller's transaction (that is, tpacall() with TPNOTRAN, TPNOBLOCK, and TPNOREPLY set).

When a service fails inside a transaction, the transaction is put into the <code>TX_ROLLBACK_ONLY</code> state. This state is treated, for most purposes, as though it were equivalent to a timeout. All further ATMI calls for this transaction (with the exception of those issued in the circumstances described in the previous paragraph) will fail with <code>TPETIME</code>.

[TPEBLOCK]

A blocking condition exists and TPNOBLOCK was specified.

[TPGOTSIG]

A signal was received and TPSIGRSTRT was not specified.

[TPEPROTO]

tpdequeue() was called improperly. There is no effect on the queue or the transaction.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file. There is no effect on the queue.

[TPEOS]

An operating system error has occurred. There is no effect on the queue.

Introduction to the C Language Application-to-Transaction Monitor Interface

[TPEDIAGNOSTIC]

Dequeuing a message from the specified queue failed. The reason for failure can be determined by the diagnostic value returned via ct1 structure.

Diagnostic The following diagnostic values are returned during the dequeuing of a message:

[QMEINVAL]

An invalid flag value was specified.

[QMEBADRMID]

An invalid resource manager identifier was specified.

[QMENOTOPEN]

The resource manager is not currently open.

[QMETRAN]

The call was not in transaction mode or was made with the TPNOTRAN flag set and an error occurred trying to start a transaction in which to dequeue the message. This diagnostic is not returned by queue managers from BEA Tuxedo release 7.1 or later.

[QMEBADMSGID]

An invalid message identifier was specified for dequeuing.

[QMESYSTEM]

A system error has occurred. The exact nature of the error is written to a log file.

[QMEOS]

An operating system error has occurred.

[QMEABORTED]

The operation was aborted. When executed within a global transaction, the global transaction has been marked rollback-only. Otherwise, the queue manager aborted the operation.

[QMEPROTO]

A dequeue was done when the transaction state was not active.

[QMEBADQUEUE]

An invalid or deleted queue name was specified.

[QMENOMSG]

No message was available for dequeuing. Note that it is possible that the message exists on the queue and another application process has read the

message from the queue. In this case, the message may be put back on the queue if that other process rolls back the transaction.

[QMEINUSE]

When dequeuing a message by message identifier or correlation identifier, the specified message is in use by another transaction. Otherwise, all messages currently on the queue are in use by other transactions. This diagnostic is not returned by queue managers from BEA Tuxedo release 7.1 or later.

[QMESHARE]

When dequeuing a message from a specified queue, the specified queue is opened *exclusively* by another application. The other application is one based on a BEA product other than the BEA Tuxedo system that opened the queue for exclusive read and/or write using the Queuing Services API (QSAPI).

See Also qmadmin(1), tpalloc(3c), tpenqueue(3c), APPQ_MIB(5), TMQUEUE(5)

tpdiscon(3c)

Name tpdiscon()—Routine for taking down a conversational service connection.

Synopsis #include <atmi.h> int tpdiscon(int cd)

Description tpdiscon() immediately tears down the connection specified by cd and generates a TPEV DISCONIMM event on the other end of the connection.

> tpdiscon() can be called only by the initiator of the conversation. tpdiscon() cannot be called within a conversational service on the descriptor with which it was invoked. Rather, a conversational service must use tpreturn () to signify that it has completed its part of the conversation. Similarly, even though a program communicating with a conversational service can issue tpdiscon(), the preferred way is to let the service tear down the connection in tpreturn (); doing so ensures correct results.

> tpdiscon() causes the connection to be torn down immediately (that is, abortive rather than orderly). Any data that has not yet reached its destination may be lost. tpdiscon () can be issued even when the program on the other end of the connection is participating in the caller's transaction. In this case, the transaction must be aborted. Also, the caller does not need to have control of the connection when tpdiscon() is called

Return Values

Upon failure, tpdiscon () returns -1 and sets tperrno to indicate the error condition.

Errors

Upon failure, tpdiscon() sets tperrno to one of the following values:

[TPEBADDESC]

cd is invalid or is the descriptor with which a conversational service was invoked.

[TPETIME]

This error code indicates that either a timeout has occurred or tpdiscon() has been attempted, in spite of the fact that the current transaction is already marked rollback only.

If the caller is in transaction mode, then either the transaction is already rollback only or a transaction timeout has occurred. The transaction is marked abort-only. (Note that calling tpdiscon() on a connection in the caller's transaction would have resulted in the transaction being marked abort-only. even if tpdiscon() had succeeded.)

If the caller is not in transaction mode, a blocking timeout has occurred.

If a transaction timeout has occurred, then, with one exception, any attempts to perform further conversational work, send new requests, or receive outstanding replies will fail with TPETIME until the transaction has been aborted. The exception is a request that does not block, expects no reply, and is not sent on behalf of the caller's transaction (that is, tpacall() with TPNOTRAN, TPNOBLOCK, and TPNOREPLY set).

When a service fails inside a transaction, the transaction is put into the <code>TX_ROLLBACK_ONLY</code> state. This state is treated, for most purposes, as though it were equivalent to a timeout. All further ATMI calls for this transaction (with the exception of those issued in the circumstances described in the previous paragraph) will fail with <code>TPETIME</code>.

[TPEPROTO]

tpdiscon() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file. The descriptor is no longer valid.

[TPEOS]

An operating system error has occurred. The descriptor is no longer valid.

See Also

tpabort(3c), tpcommit(3c), tpconnect(3c), tprecv(3c), tpreturn(3c),
tpsend(3c)

tpenqueue(3c)

Name tpenqueue ()—Routine to enqueue a message.

Synopsis #include <atmi.h>

int tpenqueue(char *qspace, char *qname, TPQCTL *ctl, char *data,

long len, long flags)

Description tpenqueue () stores a message on the queue named by *qname* in the *qspace* queue space. A queue space is a collection of queues, one of which must be *qname*.

When the message is intended for a BEA Tuxedo ATMI system server, the <code>qname</code> matches the name of a service provided by the server. The system provided server, <code>TMQFORWARD(5)</code>, provides a default mechanism for dequeuing messages from the queue and forwarding them to servers that provide a service matching the queue name. If the originator expects a reply, then the reply to the forwarded service request is stored on the originator's queue, unless otherwise specified. The originator will dequeue the reply message at a subsequent time. Queues can also be used for a reliable message transfer mechanism between any pair of BEA Tuxedo ATMI system processes (clients and/or servers). In this case, the queue name does not match a service name but some agreed upon name for transferring the message.

If data is non-NULL, it must point to a buffer previously allocated by tpalloc() and len should specify the amount of data in the buffer that should be queued. Note that if data points to a buffer of a type that does not require a length to be specified (for example, an FML fielded buffer), then len is ignored. If data is NULL, len is ignored and a message is queued with no data portion.

The message is queued at the priority defined for *qspace* unless overridden by a previous call to tpsprio().

If the caller is within a transaction and the TPNOTRAN flag is not set, the message is queued in transaction mode. This has the effect that if tpenqueue() returns successfully and the caller's transaction is committed successfully, then the message is guaranteed to be available subsequent to the transaction completing. If the caller's transaction is rolled back either explicitly or as the result of a transaction timeout or some communication error, then the message will be removed from the queue (that is, the placing of the message on the queue is also rolled back). It is not possible to enqueue then dequeue the same message within the same transaction.

The message is not queued in transaction mode if either the caller is not in transaction mode, or the TPNOTRAN flag is set. Once tpenqueue() returns successfully, the submitted message is guaranteed to be in the queue. When not in transaction mode, if a communication error or a timeout occurs, the application will not know whether or not the message was successfully stored on the queue.

The order in which messages are placed on the queue is controlled by the application via ctl data structure as described below; the default queue ordering is set when the queue is created.

The following is a list of valid flags:

TPNOTRAN

If the caller is in transaction mode and this flag is set, the message is not queued within the caller's transaction. A caller in transaction mode that sets this flag is still subject to the transaction timeout (and no other) when queuing the message. If message queuing fails, the caller's transaction is not affected.

TPNOBLOCK

The message is not enqueued if a blocking condition exists. If this flag is set and a blocking condition exists such as the internal buffers into which the message is transferred are full, the call fails and tperrno is set to TPEBLOCK. If this flag is set and a blocking condition exists because the target queue is opened *exclusively* by another application, the call fails, tperrno is set to TPEDIAGNOSTIC, and the diagnostic field of the TPQCTL structure is set to QMESHARE. In the latter case, the other application, which is based on a BEA product other than the BEA Tuxedo ATMI system, opened the queue for exclusive read and/or write using the Queuing Services API (QSAPI).

When TPNOBLOCK is not set and a blocking condition exists, the caller blocks until the condition subsides or a timeout occurs (either transaction or blocking timeout). If a timeout occurs, the call fails and tperrno is set to TPETIME.

TPNOTIME

Setting this flag signifies that the caller is willing to block indefinitely and wants to be immune to blocking timeouts. Transaction timeouts may still occur.

TPSIGRSTRT

If this flag is set and a signal interrupts any underlying system calls, the interrupted system call is reissued. If TPSIGRSTRT is not set and a signal interrupts a system call, tpenqueue() fails and tperrno is set to TPGOTSIG.

Additional information about queuing the message can be specified via ctl data structure. This information includes values to override the default queue ordering placing the message at the top of the queue or before an enqueued message; an absolute or relative time after which a queued message is made available; an absolute or relative time when a message expires and is removed from the queue; the quality of service for delivering the message; the quality of service that any replies to the message should use; a correlation identifier that aids in correlating a reply or failure message with the queued message; the name of a queue to which a reply should be enqueued; and the name of a queue to which any failure message should be enqueued.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpenqueue().

Control Parameter

The TPQCTL structure is used by the application program to pass and retrieve parameters associated with enqueuing the message. The flags element of TPQCTL is used to indicate what other elements in the structure are valid

On input to tpenqueue (), the following elements may be set in the TPQCTL structure:

The following is a list of valid bits for the flags parameter controlling input information for tpenqueue():

TPNOFLAGS

No flags or values are set. No information is taken from the control structure.

TPQTOP

Setting this flag indicates that the queue ordering be overridden and the message placed at the top of the queue. This request may not be granted depending on whether or not the queue was configured to allow overriding

the queue ordering. TPQTOP and TPQBEFOREMSGID are mutually exclusive flags.

TPQBEFOREMSGID

Setting this flag indicates that the queue ordering be overridden and the message placed in the queue before the message identified by ctl->msgid. This request may not be granted depending on whether or not the queue was configured to allow overriding the queue ordering. TPQTOP and TPQBEFOREMSGID are mutually exclusive flags. Note that the entire 32 bytes of the message identifier value are significant, so the value identified by ctl->msgid must be completely initialized (for example, padded with NULL characters).

TPQTIME ABS

If this flag is set, the message is made available after the time specified by $ctl \rightarrow deq_time$. The deq_time is an absolute time value as generated by time(2), mktime(3C), or $gp_mktime(3c)$ (the number of seconds since 00:00:00 Universal Coordinated Time—UTC, January 1, 1970). TPQTIME_ABS and TPQTIME_REL are mutually exclusive flags. The absolute time is determined by the clock on the machine where the queue manager process resides.

TPQTIME REL

If this flag is set, the message is made available after a time relative to the completion of the enqueuing operation. ctl->deq_time specifies the number of seconds to delay after the enqueuing completes before the submitted message should be available. TPQTIME_ABS and TPQTIME_REL are mutually exclusive flags.

TPOPRIORITY

If this flag is set, the priority at which the message should be enqueued is stored in ctl->priority. The priority must be in the range 1 to 100, inclusive. The higher the number, the higher the priority (that is, a message with a higher number is dequeued before a message with a lower number). For queues not ordered by priority, this value is informational.

If this flag is not set, the priority for the message is 50 by default.

TPOCORRID

If this flag is set, the correlation identifier value specified in ctl->corrid is available when a message is dequeued with tpdequeue(). This identifier accompanies any reply or failure message that is queued so that an application

can correlate a reply with a particular request. Note that the entire 32 bytes of the correlation identifier value are significant, so the value specified in <code>ctl->corrid</code> must be completely initialized (for example, padded with NULL characters).

TPQREPLYQ

If this flag is set, a reply queue named in ctl->replyqueue is associated with the queued message. Any reply to the message will be queued to the named queue within the same queue space as the request message. This string must be NULL terminated (maximum 15 characters in length).

TPOFAILUREO

If this flag is set, a failure queue named in the ctl->failurequeue is associated with the queued message. If (1) the enqueued message is processed by TMQFORWARD(), (2) TMQFORWARD was started with the -d option, and (3) the service fails and returns a non-NULL reply, a failure message consisting of the reply and its associated tpurcode is enqueued to the named queue within the same queue space as the original request message. This string must be NULL-terminated (maximum 15 characters in length).

TPQDELIVERYQOS, TPQREPLYQOS

If the TPQDELIVERYQOS flag is set, the flags specified by <code>ctl->delivery_qos</code> control the quality of service for delivery of the message. In this case, one of three mutually exclusive flags—

TPQQOSDEFAULTPERSIST, TPQQOSPERSISTENT, or

TPQQOSNONPERSISTENT—must be set in <code>ctl->delivery_qos</code>. If

TPQDELIVERYQOS is not set, the default delivery policy of the target queue dictates the delivery quality of service for the message.

If the TPQREPLYQOS flag is set, the flags specified by <code>ctl->reply_qos</code> control the quality of service for any reply to the message. In this case, one of three mutually exclusive flags—<code>TPQQOSDEFAULTPERSIST</code>, <code>TPQQOSPERSISTENT</code>, or <code>TPQQOSNONPERSISTENT</code>—must be set in <code>ctl->reply_qos</code>. The <code>TPQREPLYQOS</code> flag is used when a reply is returned from messages processed by <code>TMQFORWARD</code>. Applications not using <code>TMQFORWARD</code> to invoke services may use the <code>TPQREPLYQOS</code> flag as a hint for their own reply mechanism.

If TPQREPLYQOS is not set, the default delivery policy of the ctl->replyqueue queue dictates the delivery quality of service for any reply. Note that the default delivery policy is determined when the reply to a message is enqueued. That is, if the default delivery policy of the reply queue

is modified between the time that the original message is enqueued and the reply to the message is enqueued, the policy used is the one in effect when the reply is finally enqueued.

The following is the list of valid flags for ctl->delivery_qos and ctl->reply qos:

TPOOOSDEFAULTPERSIST

This flag specifies that the message is to be delivered using the default delivery policy specified on the target queue.

TPOOOSPERSISTENT

This flag specifies that the message is to be delivered in a persistent manner using the disk-based delivery method. Setting this flag overrides the default delivery policy specified on the target queue.

TPOOOSNONPERSISTENT

This flag specifies that the message is to be delivered in a non-persistent manner using the memory-based delivery method. Specifically, the message is queued in memory until it is dequeued. Setting this flag overrides the default delivery policy specified on the target queue. If the caller is transactional, non-persistent messages are enqueued within the caller's transaction, however, non-persistent messages are lost if the system is shut down, crashes, or the IPC shared memory for the queue space is removed.

TPQEXPTIME ABS

If this flag is set, the message has an absolute expiration time, which is the absolute time when the message will be removed from the queue. The absolute expiration time is determined by the clock on the machine where the queue manager process resides.

The absolute expiration time is indicated by the value stored in ctl->exp_time. The value of ctl->exp_time must be set to an absolute time value generated by time(2), mktime(3C), or gp_mktime(3c) (the number of seconds since 00:00:00 Universal Coordinated Time—UTC, January 1, 1970).

If an absolute time is specified that is earlier than the time of the enqueue operation, the operation succeeds, but the message is not counted for the purpose of calculating thresholds. If the expiration time is before the message availability time, the message is not available for dequeuing unless either the availability or expiration time is changed so that the availability time is before the expiration time. In addition, these messages are removed from the queue

at expiration time even if they were never available for dequeuing. If a message expires while it is within a transaction, the expiration does not cause the transaction to fail. Messages that expire while being enqueued or dequeued within a transaction are removed from the queue when the transaction ends. There is no notification that the message has expired.

TPQEXPTIME_ABS, TPQEXPTIME_REL, and TPQEXPTIME_NONE are mutually exclusive flags. If none of these flags is set, the default expiration time associated with the target queue is applied to the message.

TPQEXPTIME REL

If this flag is set, the message has a relative expiration time, which is the number of seconds *after* the message arrives at the queue that the message is removed from the queue. The relative expiration time is indicated by the value stored in ctl->exp time.

If the expiration time is before the message availability time, the message is not available for dequeuing unless either the availability or expiration time is changed so that the availability time is before the expiration time. In addition, these messages are removed from the queue at expiration time even if they were never available for dequeuing. The expiration of a message during a transaction, does not cause the transaction to fail. Messages that expire while being enqueued or dequeued within a transaction are removed from the queue when the transaction ends. There is no acknowledgment that the message has expired.

TPQEXPTIME_ABS, TPQEXPTIME_REL, and TPQEXPTIME_NONE are mutually exclusive flags. If none of these flags is set, the default expiration time associated with the target queue is applied to the message.

TPQEXPTIME NONE

Setting this flag indicates that the message should not expire. This flag overrides any default expiration policy associated with the target queue. A message can be removed by dequeuing it or by deleting it via an administrative interface.

TPQEXPTIME_ABS, TPQEXPTIME_REL, and TPQEXPTIME_NONE are mutually exclusive flags. If none of these flags is set, the default expiration time associated with the target queue is applied to the message.

Additionally, the *urcode* element of TPQCTL can be set with a user-return code. This value will be returned to the application that dequeues the message.

On output from tpenqueue(), the following elements may be set in the TPQCTL structure:

The following is a valid bit for the flags parameter controlling output information from tpenqueue(). If this flag is turned on when tpenqueue() is called, the /Q server TMQUEUE (5) populates the associated element in the structure with a message identifier. If this flag is turned off when tpenqueue() is called, TMQUEUE() does not populate the associated element in the structure with a message identifier.

TPQMSGID

If this flag is set and the call to tpenqueue() is successful, the message identifier is stored in ctl->msgid. The entire 32 bytes of the message identifier value are significant, so the value stored in ctl->msgid is completely initialized (for example, padded with NULL characters). The actual padding character used for initialization varies between releases of the BEA Tuxedo ATMI /Q component.

The remaining members of the control structure are not used on input to tpenqueue ().

If the call to tpenqueue() failed and tperrno is set to TPEDIAGNOSTIC, a value indicating the reason for failure is returned in ctl->diagnostic. The possible values are defined below in the Diagnostics section.

If this parameter is NULL, the input flags are considered to be TPNOFLAGS and no output information is made available to the application program.

Return Values

Upon failure, tpenqueue() returns -1 and sets tperrno to indicate the error condition. Otherwise, the message has been successfully queued when tpenqueue() returns

Errors Upon failure, tpenqueue() sets tperrno to one of the following values. (Unless otherwise noted, failure does not affect the caller's transaction, if one exists.)

[TPEINVAL]

Invalid arguments were given (for example, qspace is NULL, data does not point to space allocated with tpalloc(), or flags are invalid).

[TPENOENT]

Cannot access the *qspace* because it is not available (that is, the associated TMQUEUE (5) server is not available), or cannot start a global transaction due to the lack of entries in the Global Transaction Table (GTT).

[TPETIME]

This error code indicates that either a timeout has occurred or tpenqueue () has been attempted, in spite of the fact that the current transaction is already marked rollback only.

If the caller is in transaction mode, then either the transaction is already rollback only or a transaction timeout has occurred. The transaction is marked abort-only. If the caller is not in transaction mode, a blocking timeout has occurred. (A blocking timeout cannot occur if TPNOBLOCK and/or TPNOTIME is specified.)

If a transaction timeout has occurred, then, with one exception, any attempts to send new requests or receive outstanding replies will fail with TPETIME until the transaction has been aborted. The exception is a request that does not block, expects no reply, and is not sent on behalf of the caller's transaction (that is, tpacall() with TPNOTRAN, TPNOBLOCK, and TPNOREPLY set).

When a service fails inside a transaction, the transaction is put into the <code>TX_ROLLBACK_ONLY</code> state. This state is treated, for most purposes, as though it were equivalent to a timeout. All further ATMI calls for this transaction (with the exception of those issued in the circumstances described in the previous paragraph) will fail with <code>TPETIME</code>.

[TPEBLOCK]

A blocking condition exists and TPNOBLOCK was specified.

[TPGOTSIG]

A signal was received and TPSIGRSTRT was not specified.

[TPEPROTO]

tpenqueue() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

[TPEDIAGNOSTIC]

Enqueuing a message on the specified queue failed. The reason for failure can be determined by the diagnostic returned via ct1.

Diagnostic The following diagnostic values are returned during the enqueuing of a message:

[QMEINVAL]

An invalid flag value was specified.

[QMEBADRMID]

An invalid resource manager identifier was specified.

[QMENOTOPEN]

The resource manager is not currently open.

[QMETRAN]

The call was not in transaction mode or was made with the TPNOTRAN flag set and an error occurred trying to start a transaction in which to enqueue the message. This diagnostic is not returned by queue managers from BEA Tuxedo release 7.1 or later.

[QMEBADMSGID]

An invalid message identifier was specified.

[QMESYSTEM]

A system error occurred. The exact nature of the error is written to a log file.

[QMEOS]

An operating system error occurred.

[QMEABORTED]

The operation was aborted. When executed within a global transaction, the global transaction has been marked rollback-only. Otherwise, the queue manager aborted the operation.

[QMEPROTO]

An enqueue was done when the transaction state was not active.

[QMEBADQUEUE]

An invalid or deleted queue name was specified.

[QMENOSPACE]

Due to an insufficient resource, such as no space on the queue, the message with its required quality of service (persistent or non-persistent storage) was not enqueued. QMENOSPACE is returned when any of the following configured

resources is exceeded: (1) the amount of disk (persistent) space allotted to the queue space, (2) the amount of memory (non-persistent) space allotted to the queue space, (3) the maximum number of simultaneously active transactions allowed for the queue space, (4) the maximum number of messages that the queue space can contain at any one time, (5) the maximum number of concurrent actions that the Queuing Services component can handle, or (6) the maximum number of authenticated users that may concurrently use the Queuing Services component.

[QMERELEASE]

An attempt was made to enqueue a message to a queue manager that is from a version of the BEA Tuxedo system that does not support a newer feature.

[QMESHARE]

When enqueuing a message from a specified queue, the specified queue is opened *exclusively* by another application. The other application is one based on a BEA product other than the BEA Tuxedo system that opened the queue for exclusive read and/or write using the Queuing Services API (QSAPI).

```
See Also qmadmin(1), gp_mktime(3c), tpacall(3c), tpalloc(3c), tpdequeue(3c), tpinit(3c), tpsprio(3c), APPQ MIB(5), TMQFORWARD(5), TMQUEUE(5)
```

tpenvelope(3c)

Name

tpenvelope ()—Accesses the digital signature and encryption information associated with a typed message buffer.

Synopsis

```
#include <atmi.h>
int tpenvelope(char *data, long len, int occurrence, TPKEY
*outputkey, long *status, char *timestamp, long flags)
```

Description

tpenvelope() provides access to the following types of digital signature and encryption information associated with a typed message buffer:

■ Digital-signature registration requests

A sending process *explicitly* registers a digital signature request for a message buffer by calling tpsign(), or *implicitly* registers a digital signature request for a message buffer by calling tpkey_open() with the TPKEY_AUTOSIGN flag specified.

Digital signatures

Just before the message buffer is sent, the public key software generates and attaches a digital signature to the message buffer for each digital-signature registration request; a digital signature enables a receiving process to verify the signer (originator) of the message.

Encryption registration requests

A sending process *explicitly* registers an encryption (seal) request for a message buffer by calling tpseal(), or *implicitly* registers an encryption (seal) request for a message buffer by calling $tpkey_open()$ with the $tpkey_Autoencrypt$ flag specified.

Encryption envelopes

Just before the message buffer is sent, the public key software encrypts the message content and attaches an encryption envelope to the message buffer for each encryption registration request; an encryption envelope enables a receiving process to decrypt the message.

Signature and encryption information is available to both sending and receiving processes. In a sending process, digital signature and encryption information is generally in a pending state, waiting until the message is sent. In a receiving process, digital signatures have already been verified, and encryption and decryption have

already been performed. Failures in decryption or signature verification might prevent message delivery, in which case the receiving process never receives the message buffer and therefore has no knowledge of the message buffer.

data must point to a valid typed message buffer either (1) previously allocated by a process calling tpalloc() or (2) delivered by the system to a receiving process. If the message buffer is self-describing, len is ignored (and may be 0). Otherwise, len must contain the length of data in data.

There may be multiple occurrences of digital-signature registration requests, digital signatures, encryption registration requests, and encryption envelopes associated with a message buffer. The occurrences are stored in sequence, with the first item at the zero position and subsequent items in consecutive positions. The occurrence input parameter indicates which item is requested. When the value of occurrence is beyond the position of the last item, tpenvelope() fails with the TPENOENT error condition. All items may be examined by calling tpenvelope() repeatedly until TPENOENT is returned.

The handle to the key associated with a digital-signature registration request, digital signature, encryption registration request, or encryption envelope is returned via <code>outputkey</code>. The key handle returned is a separate copy of the original key opened by calling <code>tpkey_open()</code>. Properties of the key, such as the <code>PRINCIPAL</code> attribute parameter, can be obtained by calling <code>tpkey_getinfo()</code>. It is the caller's responsibility to release key handle <code>outputkey</code> by calling <code>tpkey_close()</code>.

Note: If outputkey is NULL, no key handle is returned.

The status output parameter reports the state of the digital-signature registration request, digital signature, encryption registration request, or encryption envelope. If the value of the status is not NULL, it is set to one of the following states:

TPSIGN PENDING

A digital signature has been requested on behalf of the *signer* principal associated with the corresponding private key, and will be generated when the message buffer is transmitted from this process.

TPSIGN OK

The digital signature has been verified.

TPSIGN TAMPERED MESSAGE

The digital signature is not valid because the content of the message buffer has been altered.

TPSIGN TAMPERED CERT

The digital signature is not valid because the signer's digital certificate has been altered.

TPSIGN REVOKED CERT

The digital signature is not valid because the signer's digital certificate has been revoked.

TPSIGN POSTDATED

The digital signature is not valid because its timestamp is too far into the future.

TPSIGN EXPIRED CERT

The digital signature is not valid because the signer's digital certificate has expired.

TPSIGN EXPIRED

The digital signature is not valid because its timestamp is too old.

TPSIGN UNKNOWN

The digital signature is not valid because the signer's digital certificate was issued by an unknown Certification Authority (CA).

TPSEAL PENDING

An encryption (seal) has been requested for the *recipient* principal associated with the corresponding public key, and will be performed when the message buffer is transmitted from this process.

TPSEAL OK

The encryption envelope is valid.

TPSEAL TAMPERED CERT

The encryption envelope is not valid because the recipient's digital certificate has been altered.

TPSEAL REVOKED CERT

The encryption envelope is not valid because the recipient's digital certificate has been revoked.

TPSEAL EXPIRED CERT

The encryption envelope is not valid because the recipient's digital certificate has expired.

TPSEAL UNKNOWN

The encryption envelope is not valid because the recipient's digital certificate was issued by an unknown CA.

The <code>timestamp</code> output parameter contains the digital signature's timestamp according to the local clock on the machine where the digital signature was generated. The integrity of this value is protected by the associated digital signature. The memory location indicated by <code>timestamp</code> is set to the NULL-terminated signature time in format <code>YYYYMMDDHHMMSS</code>, where <code>YYYY=year</code>, <code>MM=month</code>, <code>DD=day</code>, <code>HH=hour</code>, <code>MM=minute</code>, and <code>SS=second</code>. <code>timestamp</code> may be NULL, in which case no value is returned. Encryption seals do not contain timestamps, and the memory location indicated by <code>timestamp</code> is unchanged.

The flags parameter may be set to one of the following values:

- TPKEY_REMOVE—The item at position occurrence is removed (that is, it is no longer associated with the buffer). Output parameters outputkey, status, and timestamp related to the item are captured before the item is removed. Items at subsequent positions are shifted down by one, so there are never any gaps in the numbering of occurrence.
- TPKEY_REMOVEALL—All items associated with the message buffer are removed. The output parameters outputkey, status, and timestamp are not returned.
- TPKEY_VERIFY—All digital signatures associated with the message buffer are reverified. The status of a signature may change after reverification. For example, if a message buffer has been modified by a receiving process, the status of the originator's signature changes from TPSIGN_OK to TPSIGN TAMPERED MESSAGE.

Return Values On failu

On failure, this function returns -1 and sets tperrno to indicate the error condition.

Errors [TPEINVAL]

Invalid arguments were given. For example, the value of data is NULL or the value assigned to flags is unrecognized.

[TPENOENT]

This occurrence does not exist.

[TPESYSTEM]

An error occurred. Consult the system error log file for details.

tperrordetail(3c)

Name tperrordetail()—Gets additional detail about an error generated from the last

BEA Tuxedo ATMI system call.

Synopsis #include <atmi.h>

int tperrordetail(long flags)

Description tperrordetail() returns additional detail related to an error produced by the last

BEA Tuxedo ATMI system routine called in the current thread. tperrordetail() returns a numeric value that is also represented by a symbolic name. If the last BEA Tuxedo ATMI system routine called in the current thread did not produce an error, then tperrordetail() will return zero. Therefore, tperrordetail() should be called after an error has been indicated; that is, when tperrno has been set.

Currently *flags* is reserved for future use and must be set to 0.

A thread in a multithreaded application may issue a call to tperrordetail() while running in any context state, including TPINVALIDCONTEXT.

Return Values

Upon failure, tperrordetail() returns a -1 and sets tperrno to indicate the error condition

These are the symbolic names and meaning for each numeric value that tperrordetail() may return. The order in which these are listed is not significant and does not imply precedence.

TPED CLIENTDISCONNECTED

A Jolt client is disconnected currently. The TPACK flag is used in a tpnotify() call and the target of tpnotify() is a currently disconnected Jolt client. When tpnotify() fails, a subsequent call to tperrordetail() with no intermediate ATMI calls will return TPED CLIENTDISCONNECTED.

TPED DECRYPTION FAILURE

A process receiving an encrypted message cannot decrypt the message. This error most likely occurs because the process does not have access to the private key required to decrypt the message.

When a call fails due to this error, a subsequent call to tperrordetail() with no intermediate ATMI calls will return TPED DECRYPTION FAILURE.

TPED DOMAINUNREACHABLE

A domain is unreachable. Specifically, a domain configured to satisfy a request that a local domain cannot service was not reachable when a request

was made. After the request failure, a subsequent call to tperrordetail () with no intermediate ATMI calls will return TPED DOMAINUNREACHABLE.

The following table indicates the corresponding values returned by tperrno when calls to tpcall(), tpgetrply(), or tprecv() fail because of an unreachable domain. The error detail returned by a subsequent call to tperrordetail() is TPED DOMAINUNREACHABLE.

ATMI Call	tperrno	Error Detail
tpcall	TPESVCERR	TPED_DOMAINUNREACHABLE
tpgetrply	TPESVCERR	TPED_DOMAINUNREACHABLE
tprecv	TPEEVENT TPEV_SVCERR	TPED_DOMAINUNREACHABLE

Note that the TPED_DOMAINUNREACHABLE feature applies to BEA Tuxedo Domains only. It does not apply to other domains products such as Connect OSI TP Domains and Connect SNA Domains.

TPED INVALID CERTIFICATE

A process receiving a digitally signed message cannot verify the digital signature because the associated digital certificate is invalid. This error most likely occurs because the digital certificate has expired, the digital certificate was issued by an unknown Certification Authority (CA), or the digital certificate has been altered

When a call fails due to this error, a subsequent call to tperrordetail() with no intermediate ATMI calls will return TPED INVALID CERTIFICATE.

TPED INVALID SIGNATURE

A process receiving a digitally signed message cannot verify the digital signature because the signature is invalid. This error most likely occurs because the message has been altered, the timestamp for the digital signature is too old, or the timestamp for the digital signature is too far into the future.

When a call fails due to this error, a subsequent call to tperrordetail() with no intermediate ATMI calls will return TPED INVALID SIGNATURE.

TPED INVALIDCONTEXT

A thread is blocked in an ATMI call when another thread terminates its context. Specifically, any thread blocked in an ATMI call when another thread terminates its context will return from the ATMI call with a failure

return; tperrno is set to TPESYSTEM. A subsequent call to tperrordetail() with no intermediate ATMI calls will return TPED INVALIDCONTEXT.

TPED INVALID XA TRANSACTION

An attempt was made to start a transaction but the NO_XA flag was turned on in this domain.

TPED NOCLIENT

No client exists. The TPACK flag is used in a tpnotify() call but there is no target for tpnotify(). When tpnotify() fails, tperrno is set to TPENOENT. A subsequent call to tperrordetail() with no intermediate ATMI calls will return TPED NOCLIENT.

TPED NOUNSOLHANDLER

A client does not have an unsolicited handler set. The TPACK flag is used in a tpnotify() call and the target of the tpnotify() is in a BEA Tuxedo ATMI session, but it has not set an unsolicited notification handler. When tpnotify() fails, tperrno is set to TPENOENT. A subsequent call to tperrordetail() with no intermediate ATMI calls will return TPED NOUNSOLHANDLER.

TPED SVCTIMEOUT

A server was terminated due to a service timeout. The service timeout is controlled by the value of SVCTIMEOUT in the UBBCONFIG file or TA_SVCTIMEOUT in T_SERVER and T_SERVICE classes in the TM_MIB. When a call fails due to this error, a subsequent call to tperrordetail() with no intermediate ATMI calls will return TPED SVCTIMEOUT.

TPED TERM

A Workstation client has been disconnected from the application. When a call fails due to this error, a subsequent call to tperrordetail() with no intermediate ATMI calls will return TPED TERM.

Errors Upon failure, tperrordetail() sets tperror to one of the following values:

TPEINVAL

flags not set to zero

See Also Introduction to the C Language Application-to-Transaction Monitor Interface, tpstrerrordetail(3c), tperrno(5)

tpexport(3c)

Name

tpexport () —Converts a typed message buffer into an exportable, machine-independent string representation, that includes digital signatures and encryption envelopes.

Synopsis

```
#include <atmi.h>
int tpexport(char *ibuf, long ilen, char *ostr, long *olen,
long flags)
```

Description

tpexport () converts a typed message buffer into an externalized representation. An externalized representation is a message buffer that does *not* include any BEA Tuxedo ATMI header information that is normally added to a message buffer just before the buffer is transmitted.

The externalized representation may be transmitted between processes, machines, or BEA Tuxedo ATMI applications via any communication mechanism. It may be archived on permanent storage, and remains valid after a system shutdown and reboot.

An externalized representation includes:

- Any digital signatures associated with *ibuf*. They are verified later when the buffer is imported.
- Any encryption envelopes associated with ibuf. The buffer content remains protected by encryption. Only specified recipients with access to a valid private key for decryption may later import the buffer.

ibuf must point to a valid typed message buffer either (1) previously allocated by a process calling tpalloc() or (2) delivered by the system to a receiving process. *ilen* specifies how much of *ibuf* to export. Note that if *ibuf* points to a buffer type for which a length need not be specified (for example, an FML fielded buffer), then *ilen* is ignored (and may be 0).

ostr is a pointer to the output area that will hold an externalized representation of the buffer's content and associated properties. If TPEX_STRING is set in flags, then the externalized format will be a string type. Otherwise, the output length is determined by *olen and may contain embedded NULL bytes.

On input, *olen specifies the maximum storage size available at ostr. On output *olen is set to the actual number of bytes written to ostr (including a terminating NULL character if TPEX_STRING is set in flags).

The flags argument may be set to TPEX_STRING if string format (base 64 encoded) is desired for the output buffer. Otherwise, the output will be binary.

Return Values

On failure, this function returns -1 and sets tperrno to indicate the error condition.

Errors

[TPEINVAL]

Invalid arguments were given. For example, the value of *ibuf* is NULL or the value of *flags* is not set correctly.

[TPEPERM]

Permission failure. The cryptographic service provider was not able to access a private key necessary to produce a digital signature.

[TPESYSTEM]

An error occurred. Consult the system error log file for details.

[TPELIMIT]

Insufficient output storage was provided. *olen is set to the necessary amount of space.

See Also

tpimport(3c)

tpforward(3c)

Name tpforward()—Routine for forwarding a service request to another service routine.

Description tpforward() allows a service routine to forward a client's request to another service routine for further processing. tpforward() acts like tpreturn() in that it is the last call made in a service routine. Like tpreturn(), tpforward() should be called from within the service routine dispatched to ensure correct return of control to the BEA Tuxedo ATMI system dispatcher. tpforward() cannot be called from within a conversational service

This function forwards a request to the service named by svc using data pointed to by data. The service name must not begin with a dot. A service routine forwarding a request receives no reply. After the request is forwarded, the service routine returns to the communication manager dispatcher and the server is free to do other work. Note that because no reply is expected from a forwarded request, the request may be forwarded without error to any service routine in the same executable as the service that forwarded the request.

If the service routine is in transaction mode, <code>tpforward()</code> puts the caller's portion of the transaction in a state where it may be completed when the originator of the transaction issues either <code>tpcommit()</code> or <code>tpabort()</code>. If a transaction was explicitly started with <code>tpbegin()</code> while in a service routine, the transaction must be ended with either <code>tpcommit()</code> or <code>tpabort()</code> before calling <code>tpforward()</code>. Thus, all services in a "forward chain" are either all started in transaction mode or none are.

The last server in a forward chain sends a reply back to the originator of the request using tpreturn(). In essence, tpforward() transfers to another server the responsibility of sending a reply back to the awaiting requester.

tpforward() should be called after receiving all replies expected from service requests initiated by the service routine. Any outstanding replies which are not received will automatically be dropped by the communication manager dispatcher upon receipt. In addition, the descriptors for those replies become invalid and the request is not forwarded to svc.

data points to the data portion of a reply to be sent. If data is non-NULL, it must point to a buffer previously obtained by a call to tpalloc(). If this is the same buffer passed to the service routine upon its invocation, then its disposition is up to the BEA Tuxedo ATMI system dispatcher; the service routine writer does not have to worry about

whether it is freed or not. In fact, any attempt by the user to free this buffer will fail. However, if the buffer passed to tpforward() is not the same one with which the service is invoked, then tpforward() will free that buffer. <code>len</code> specifies the amount of the data buffer to be sent. If <code>data</code> points to a buffer which does not require a length to be specified, (for example, an FML fielded buffer), then <code>len</code> is ignored (and can be 0). If <code>data</code> is NULL, then <code>len</code> is ignored and a request with zero length data is sent.

The *flags* argument is reserved for future use and should be set to 0 (zero).

Return Values

A service routine does not return any value to its caller, the communication manager dispatcher. Thus, tpforward() is declared as a void. See tpreturn(3c) for a more extensive discussion.

Frrors

If any errors occur either in the handling of the parameters passed to the function or in its processing, a "failed" message is sent back to the original requester (unless no reply is to be sent). The existence of outstanding replies or subordinate connections, or the caller's transaction being marked abort-only, qualify as failures which generate failed messages.

If either SVCTIMEOUT in the UBBCONFIG file or TA_SVCTIMEOUT in the TM_MIB is non-zero, the event, TPEV_SVCERR is returned when a service timeout occurs.

Failed messages are detected by the requester with the TPESVCERR error indication. When such an error occurs, the caller's data is not sent. Also, this error causes the caller's current transaction to be marked abort-only.

If a transaction timeout occurs, either during the service routine or while the request is being forwarded, the requester waiting for a reply with either tpcall() or tpgetrply() will get a TPETIME error return. When a service fails inside a transaction, the transaction times out and is put into the TX_ROLLBACK_ONLY state. All further ATMI calls for that transaction will fail with TPETIME. The waiting requester will not receive any data. Service routines, however, are expected to terminate using either tpreturn() or tpforward(). A conversational service routine must use tpreturn(); it cannot use tpforward().

If a service routine returns without using either tpreturn() or tpforward() (that is, if it uses the C language return statement or simply "falls out of the function") or if tpforward() is called from a conversational server, the server will print a warning message in a log file and return a service error to the original requester. All open connections to subordinates will be disconnected immediately, and any outstanding asynchronous replies will be marked stale. If the server was in transaction mode at the time of failure, the transaction is marked abort-only. Note also that if either

Introduction to the C Language Application-to-Transaction Monitor Interface

tpreturn() or tpforward() are used outside of a service routine (for example, in clients, or in tpsvrinit() or tpsvrdone()), then these routines simply return having no effect.

tpfree(3c)

Name tpfree()—Routine for freeing a typed buffer.

Description The argument to tpfree() is a pointer to a buffer previously obtained by either tpalloc() or tprealloc(). If ptr is NULL, no action occurs. Undefined results will

occur if ptr does not point to a typed buffer (or if it points to space previously freed with tpfree()). Inside service routines, tpfree() returns and does not free the buffer if

if ptr points to the buffer passed into a service routine.

Some buffer types require state information or associated data to be removed as part of freeing a buffer. tpfree() removes any of these associations (in a communication manager-specific manner) before a buffer is freed.

Once tpfree () returns, ptr should not be passed as an argument to any BEA Tuxedo ATMI system routine or used in any other manner.

A thread in a multithreaded application may issue a call to tpfree() while running in any context state, including TPINVALIDCONTEXT.

When freeing an FML32 buffer using tpfree(), the routine recursively frees all embedded buffers to prevent memory leaks. In order to preserve the embedded buffers, you should assign the associated pointer to NULL before issuing the tpfree() command. As stated above, if *ptr* is NULL, no action occurs.

Return Values tpfree() does not return any value to its caller. Thus, it is declared as a void.

This function should not be used in concert with malloc(), realloc(), or free() in the C library (for example, a buffer allocated with tpalloc() should not be freed with free()).

See Also Introduction to the C Language Application-to-Transaction Monitor Interface, tpalloc(3c), tprealloc(3c)

Usage

tpgetadmkey(3c)

Name tpgetadmkey()—Gets administrative authentication key.

Synopsis #include <atmi.h>

long tpgetadmkey(TPINIT *tpinfo)

Description tpgetadmkey() is available for application use by an application specific

authentication server. It returns an application security key suitable for assignment to the indicated user for the purpose of administrative authentication. This routine must be called with a client name (that is, tpinfo->cltname) of either tpsysadm() or

tpsysop(); otherwise, a valid administrative key will not be returned.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed

to issue a call to tpgetadmkey().

Return Values Upon success, tpgetadmkey() returns a non-0 value with the high-order bit

(0x80000000) set; otherwise it returns 0. Zero may be returned if tpinfo is NULL, tpinfo->cltname is not tpsysadm() or tpsysop(), or lastly if the effective user ID

is not the configured application administrator for this site.

Errors A zero return value is the only indication that a valid administrative key was not

assigned.

Portability This interface is available only on UNIX system sites running BEA Tuxedo release 5.0

or later.

See Also tpaddusr(1), tpusradd(1), tpinit(3c), AUTHSVR(5)

Setting Up a BEA Tuxedo Application

Administering a BEA Tuxedo Application at Run Time

tpgetctxt(3c)

Name tpgetctxt()—Retrieves a context identifier for the current application association.

Synopsis #include <atmi.h>
 int tpgetctxt(TPCONTEXT T *context, long flags)

Description

tpgetctxt() retrieves an identifier that represents the current application context and places that identifier in *context*. This function operates on a per-thread basis in a multithreaded environment, and on a per-process basis in a non-threaded environment.

Typically, a thread:

- 1. Calls tpinit()
- 2. Calls tpgetctxt()
- 3. Handles the value of context as follows:
 - In a multithreaded application—passes the value of context to another thread in the same process so the other thread can call tpsetctxt().
 - In a single-threaded or multithreaded application—saves this context identifier for itself so it can switch back to the indicated context later.

The second argument, flags, is not currently used and must be set to 0.

tpgetctxt() may be called in single-context applications as well as in multicontext applications.

A thread in a multithreaded application may issue a call to tpgetctxt() while running in any context state, including TPINVALIDCONTEXT.

Return Values

Upon successful completion, tpgetctxt() returns a non-negative value. Context is set to the current context ID, which may be represented by any of the following:

- A context ID greater than 0, indicating a context in a multicontexted application.
- TPSINGLECONTEXT, indicating that the current thread has successfully executed tpinit() without the TPMULTICONTEXTS flag, or that the current thread was just created in a process that has successfully executed tpinit() without the TPMULTICONTEXTS flag. The value of TPSINGLECONTEXT is 0.
- TPNULLCONTEXT, indicating that the current thread is not associated with a context.

■ TPINVALIDCONTEXT, indicating that the current thread is in the invalid context state. If a thread in a multicontexted client issues a call to tpterm() while other threads in the same context are still working, the working threads are placed in the TPINVALIDCONTEXT context. The value of TPINVALIDCONTEXT is -1.

A thread in the TPINVALIDCONTEXT state is prohibited from issuing calls to most ATMI functions. For a complete list of functions that may and may not be called, see the Introduction to the C Language Application-to-Transaction Monitor Interface

For details about the TPINVALIDCONTEXT context state, see tpterm (3c).

Upon failure, tpgetctxt () returns a value of -1 and sets tperrno to indicate the error condition.

Errors Upon failure, tpgetctxt() sets tperrno to one of the following values:

[TPEINVAL]

Invalid arguments have been given. For example, the value of *context* is NULL or the value of *flags* is not 0.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error has been written to a log file.

[TPEOS]

An operating system error has occurred.

See Also Introduction to the C Language Application-to-Transaction Monitor Interface, tpsetctxt(3c), tpterm(3c)

tpgetlev(3c)

Name tpgetlev()—Routine for checking if a transaction is in progress.

Synopsis #include <atmi.h>
 int tpgetlev()

Description tpgetlev() returns to the caller the current transaction level. Currently, the only

levels defined are 0 and 1.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed

to issue a call to tpgetlev().

Return Values Upon successful completion, tpgetlev () returns either a 0 to indicate that no

transaction is in progress, or 1 to indicate that a transaction is in progress;

Upon failure, tpgetlev() returns -1 and sets tperrno to indicate the error condition.

Errors Upon failure, tpgetlev() sets tperrno to one of the following values:

[TPEPROTO]

tpgetlev() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

Notices

When using <code>tpbegin()</code>, <code>tpcommit()</code> and <code>tpabort()</code> to delineate a BEA Tuxedo ATMI system transaction, it is important to remember that only the work done by a resource manager that meets the XA interface (and is linked to the caller appropriately) has transactional properties. All other operations performed in a transaction are not affected by either <code>tpcommit()</code> or <code>tpabort()</code>. See <code>buildserver(1)</code> for details on linking resource managers that meet the XA interface into a server such that operations performed by that resource manager are part of a BEA Tuxedo ATMI system transaction.

See Also tpabort(3c), tpbegin(3c), tpcommit(3c), tpscmt(3c)

tpgetmbenc(3c)

Name tpgetmbenc()—Gets the code-set encoding name from a typed buffer.

Synopsis

```
#include <atmi.h>
extern int tperrno;
int
tpgetmbenc (char *bufp, char *enc name, long flags)
```

Description

This function is used to get the codeset encoding name sent with a typed buffer. This name can be compared to a target codeset if a conversion is required (see tpconvmb(3c)).

The bufp argument is a valid pointer to a typed buffer message.

The <code>enc_name</code> argument will be set to the encoding name, found in <code>bufp</code>, upon successful execution of this function. The returned string will be NULL terminated. The user must take care to allocate a buffer large enough to hold the encoding name plus the NULL terminator (see <code>NL_LANGMAX</code> in <code><liimits.h></code>). An MBSTRING typed buffer without the encoding name set is invalid.

The *flags* argument is not currently used and should be set to zero.

Return Values

Upon success, tpgetmbenc() returns a value of 0. This function returns -1 on error and sets tperrno as described below for each function. The function may fail for the following reasons.

```
[TPEINVAL]
```

enc_name or bufp argument is NULL.

[TPEPROTO]

This error occurs if bufp can not provide an encoding name.

[TPESYSTEM]

A Tuxedo system error has occurred. (e.g. bufp does not correspond to a valid Tuxedo buffer).

```
See Also tpalloc(3c), tpconvmb(3c), tpsetmbenc(3c)
```

tpgetrply(3c)

Name tpgetrply()—Routine for getting a reply from a previous request.

Synopsis #include <atmi.h>
 int tpgetrply(int *cd, char **data, long *len, long flags)

Description tpgetrply() returns a reply from a previously sent request. This function's first argument, cd, points to a call descriptor returned by tpacall(). By default, the

function waits until the reply matching *cd arrives or a timeout occurs.

data must be the address of a pointer to a buffer previously allocated by tpalloc() and <code>len</code> should point to a long that tpgetrply() sets to the amount of data successfully received. Upon successful return, *data points to a buffer containing the reply and *len contains the size of the data. FML and FML32 buffers often assume a minimum size of 4096 bytes; if the reply is larger than 4096, the size of the buffer is increased to a size large enough to accommodate the data being returned. As of release 6.4, the default allocation for buffers is 1024 bytes. Also, historical information is maintained on recently used buffers, allowing a buffer of optimal size to be reused as a return buffer.

Buffers on the sending side that may be only partially filled (for example, FML or STRING buffers) will have only the amount that is used send. The system may then enlarge the received data size by some arbitrary amount. This means that the receiver may receive a buffer that is smaller than what was originally allocated by the sender, yet larger than the data that was sent.

The receive buffer may grow, or it may shrink, and its address almost invariably changes, as the system swaps buffers around internally. To determine whether (and how much) a reply buffer changed in size, compare its total size before <code>tpgetrply()</code> was issued with * <code>len</code>. See the "Introduction to the C Language Application-to-Transaction Monitor Interface" for more information about buffer management.

If *len is 0, then the reply has no data portion and neither *data nor the buffer it points to were modified.

It is an error for *data or len to be NULL.

Within any particular context of a multithreaded program:

■ Calls to tpgetrply (TPGETANY) and tpgetrply () for a specific handle cannot be issued concurrently.

■ Multiple calls to tpgetrply(TPGETANY) cannot be issued concurrently.

Any tpgetrply() call that would, if issued, cause a violation of either of these restrictions, returns -1 and sets tperrno to TPEPROTO.

It is acceptable to issue:

- Concurrent calls to tpgetrply() for different handles.
- A call to tpgetrply(TPGETANY) in a single context concurrently with a call to tpgetrply(), with or without TPGETANY, in a different context.

The following is a list of valid flags:

TPGETANY

This flag signifies that tpgetrply() should ignore the descriptor pointed to by cd, return any reply available and set cd to point to the call descriptor for the reply returned. If no replies exist, tpgetrply() by default will wait for one to arrive.

TPNOCHANGE

By default, if a buffer is received that differs in type from the buffer pointed to by *data, then *data's buffer type changes to the received buffer's type so long as the receiver recognizes the incoming buffer type. When this flag is set, the type of the buffer pointed to by *data is not allowed to change. That is, the type and subtype of the received buffer must match the type and subtype of the buffer pointed to by *data.

TPNOBLOCK

tpgetrply() does not wait for the reply to arrive. If the reply is available, then tpgetrply() gets the reply and returns. When this flag is not specified and a reply is not available, the caller blocks until the reply arrives or a timeout occurs (either transaction or blocking timeout).

TPNOTIME

This flag signifies that the caller is willing to block indefinitely for its reply and wants to be immune to blocking timeouts. Transaction timeouts may still occur.

TPSIGRSTRT

If a signal interrupts any underlying system calls, then the interrupted system call is reissued.

Except as noted below, *cd is no longer valid after its reply is received.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpgetrply().

Return Values

Upon successful return from tpgetrply() or upon return where tperrno is set to TPESVCFAIL, tpurcode() contains an application defined value that was sent as part of tpreturn().

Upon failure, tpgetrply() returns -1 and sets tperrno to indicate the error condition.

Frrors

Upon failure, tpgetrply() sets tperrno as indicated below. Note that if TPGETANY is not set, then *cd is invalidated unless otherwise stated. If TPGETANY is set, then cd points to the descriptor for the reply on which the failure occurred; if an error occurred before a reply could be retrieved, then cd points to 0. Also, the failure does not affect the caller's transaction, if one exists, unless otherwise stated. If a call fails with a particular tperrno value, a subsequent call to tperrordetail() with no intermediate ATMI calls, may provide more detailed information about the generated error. Refer to the tperrordetail(3c) reference page for more information.

[TPEINVAL]

Invalid arguments were given (for example, cd, data, *data or len is NULL or flags are invalid). If cd is non-NULL, then it is still valid after this error and the reply remains outstanding.

[TPEOTYPE]

Either the type and subtype of the reply are not known to the caller; or, TPNOCHANGE was set in flags and the type and subtype of *data do not match the type and subtype of the reply sent by the service. Regardless, neither *data, its contents nor *len are changed. If the reply was to be received on behalf of the caller's current transaction, then the transaction is marked abort-only since the reply is discarded.

[TPEBADDESC]

cd points to an invalid descriptor.

[TPETIME]

This error code indicates that either a timeout has occurred or tpgetrply() has been attempted, in spite of the fact that the current transaction is already marked rollback only.

If the caller is in transaction mode, then either the transaction is already rollback only or a transaction timeout has occurred. The transaction is marked abort-only. If the caller is not in transaction mode, a blocking timeout has

occurred. (A blocking timeout cannot occur if TPNOBLOCK and/or TPNOTIME is specified.) In either case, no changes are made to *data, its contents, or *len. *cd remains valid unless the caller is in transaction mode (and TPGETANY has not been set).

If a transaction timeout has occurred, then, with one exception, any attempts to send new requests or receive outstanding replies will fail with TPETIME until the transaction has been aborted. The exception is a request that does not block, expects no reply, and is not sent on behalf of the caller's transaction (that is, tpacall() with TPNOTRAN, TPNOBLOCK, and TPNOREPLY set).

When a service fails inside a transaction, the transaction is put into the TX_ROLLBACK_ONLY state. This state is treated, for most purposes, as though it were equivalent to a timeout. All further ATMI calls for this transaction (with the exception of those issued in the circumstances described in the previous paragraph) will fail with TPETIME.

[TPESVCFAIL]

The service routine sending the caller's reply called tpreturn() with TPFAIL. This is an application-level failure. The contents of the service's reply, if one was sent, is available in the buffer pointed to by *data. If the service request was made on behalf of the caller's transaction, then the transaction is marked abort-only. Note that regardless of whether the transaction has timed out, the only valid communications before the transaction is aborted are calls to tpacall() with TPNOREPLY, TPNOTRAN, and TPNOBLOCK set.

[TPESVCERR]

A service routine encountered an error either in tpreturn() or tpforward() (for example, bad arguments were passed). No reply data is returned when this error occurs (that is, neither *data, its contents nor *len are changed). If the service request was made on behalf of the caller's transaction, then the transaction is marked abort-only. Note that regardless of whether the transaction has timed out, the only valid communications before the transaction is aborted are calls to tpacall() with TPNOREPLY, TPNOTRAN, and TPNOBLOCK set. If either SVCTIMEOUT in the UBBCONFIG file or TA_SVCTIMEOUT in the TM_MIB is non-zero, TPESVCERR is returned when a service timeout occurs.

[TPEBLOCK]

A blocking condition exists and TPNOBLOCK was specified. *cd remains valid

[TPGOTSIG]

A signal was received and TPSIGRSTRT was not specified.

[TPEPROTO]

tpgetrply() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred. If a message queue on a remote location is filled, TPEOS may possibly be returned.

See Also

tpacall(3c), tpalloc(3c), tpcancel(3c), tperrordetail(3c),
tprealloc(3c), tpreturn(3c), tpstrerrordetail(3c), tptypes(3c)

tpgprio(3c)

Name tpgprio()—Routine for getting a service request priority.

Synopsis #include <atmi.h>
 int tpgprio(void)

Description

tpgprio() returns the priority for the last request sent or received by the current thread in its curent context. Priorities can range from 1 to 100, inclusive, with 100 being the highest priority. tpgprio() may be called after tpcall() or tpacall(), (also tpenqueue(), or tpdequeue(), assuming the queued management facility is installed), and the priority returned is for the request sent. Also, tpgprio() may be called within a service routine to find out at what priority the invoked service was sent. tpgprio() may be called any number of times and will return the same value until the next request is sent.

In a multithreaded application tpgprio() operates on a per-thread basis.

Because the conversation primitives are not associated with priorities, issuing tpsend() or tprecv() has no affect on the priority returned by tpgprio(). Also, there is no priority associated with a conversational service routine unless a tpcall() or tpacall() is done within that service.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpgprio().

Return Values

Upon success, tpgprio() returns a request's priority;

Upon failure, tpgprio () returns -1 and sets tperrno to indicate the error condition.

Frrors

Upon failure, tpgprio() sets tperrno to one of the following values:

[TPENOENT]

tpgprio() was called and no requests (via tpcall() or tpacall()) have been sent, or it is called within a conversational service for which no requests have been sent.

[TPEPROTO]

tpgprio() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

See Also

 $\label{eq:condition} \begin{array}{l} \text{tpacall (3c), tpcall (3c), tpdequeue (3c), tpenqueue (3c), tpservice (3c),} \\ \text{tpsprio (3c)} \end{array}$

tpimport(3c)

Name

tpimport ()—Converts an externalized representation of a message buffer into a typed message buffer.

Synopsis

#include <atmi.h>
int tpimport(char *istr, long ilen, char **obuf, long *olen,
long flags)

Description

tpimport() converts an externalized representation of a message buffer into a typed message buffer. An externalized representation is a message buffer that does *not* include any BEA Tuxedo ATMI header information that is normally added to a message buffer just before the buffer is transmitted. A process converts a typed message buffer into an externalized representation by calling the tpexport() function.

Any digital signatures associated with *istr* are verified when the buffer is imported, and are available for examination after importing via tpenvelope().

If the *istr* buffer representation is encrypted, the importing process must have access to a valid private key for decryption. Decryption is performed automatically during the importing process.

If TPEX_STRING is *not* set in *flags*, then *ilen* contains the length of the binary data contained in *istr*. If *ilen* is 0, *istr* is assumed to point to a NULL-terminated string, and the TPEX_STRING flag is inferred.

*obuf must point to a valid typed message buffer either (1) previously allocated by a process calling tpalloc() or (2) delivered by the system to a receiving process. The buffer will be reallocated as necessary to accommodate the result, and its buffer type or subtype may change.

*olen is set to the amount of valid data contained in the output buffer. If olen is NULL on input, it is ignored.

The *flags* argument should be set to TPEX_STRING if the input externalized representation is in string format (base 64 encoded). Otherwise, the input is in binary format of length *ilen*.

Return Values

On failure, this function returns -1 and sets tperrno to indicate the error condition.

Errors [T

[TPEINVAL]

Invalid arguments were given. For example, the value of *istr* is NULL or the *flags* parameter is not set correctly.

[TPEPERM]

Permission failure. The cryptographic service provider was not able to access a private key necessary for decryption.

[TPEPROTO]

A protocol failure occurred. The failure involves an invalid data format in istr or a digital signature that failed verification.

[TPESYSTEM]

An error occurred. Consult the system error log file for more details.

See Also tpenvelope(3c), tpexport(3c)

tpinit(3c)

Name tpinit()—Joins an application.

Synopsis #include <atmi.h>

int tpinit(TPINIT *tpinfo)

Description

tpinit() allows a client to join a BEA Tuxedo ATMI system application. Before a client can use any of the BEA Tuxedo ATMI system communication or transaction routines, it must first join a BEA Tuxedo ATMI system application.

tpinit() has two modes of operation: single-context mode and multicontext mode, which will be discussed in detail below. Because calling tpinit() is optional when in single-context mode, a single-context client may also join an application by calling many ATMI routines (for example, tpcall()), which transparently call tpinit() with tpinfo set to NULL. A client may want to call tpinit() directly so that it can set the parameters described below. In addition, tpinit() must be used when multicontext mode is required, when application authentication is required (see the description of the SECURITY keyword in UBBCONFIG(5)), or when the application wishes to supply its own buffer type switch (see typesw(5)). After tpinit() successfully returns, the client can initiate service requests and define transactions.

In single-context mode, if tpinit() is called more than once (that is, if it is called after the client has already joined the application), no action is taken and success is returned.

In a multithreaded client, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpinit(). To join a BEA Tuxedo ATMI application, a multithreaded Workstation client must always call tpinit() with the TPMULTICONTEXTS flag set, even if the client is running in single-context mode.

Note: The TPMULTICONTEXTS mode of tpinit will continue to work properly when the TMNOTHREADS environment variable is set to yes. Setting this environment variable to yes turns off multithreaded processing for applications that do not use threads.

Description of the TPINFO Structure

tpinit()'s argument, tpinfo, is a pointer to a typed buffer of type TPINIT and a NULL subtype. TPINIT is a buffer type that is typedefed in the atmi.h header file. The buffer must be allocated via tpalloc() prior to calling tpinit(). The buffer should be freed using tpfree() after calling tpinit(). The TPINIT typed buffer structure includes the following members:

```
char usrname[MAXTIDENT+2];
char cltname[MAXTIDENT+2];
char passwd[MAXTIDENT+2];
char grpname[MAXTIDENT+2];
long flags;
long datalen;
long data;
```

The values of usrname, cltname, grpname, and passwd are all NULL-terminated strings. usrname is a name representing the caller. cltname is a client name whose semantics are application defined. The value sysclient is reserved by the system for the cltname field. The usrname and cltname fields are associated with the client at tpinit() time and are used for both broadcast notification and administrative statistics retrieval. They should not have more characters than MAXTIDENT, which is defined as 30. passwd is an application password in unencrypted format that is used for validation against the application password. The passwd is limited to 30 characters. grpname is used to associate the client with a resource manager group name. If grpname is set to a 0-length string, then the client is not associated with a resource manager and is in the default client group. The value of grpname must be the NULL string (0-length string) for Workstation clients. Note that grpname is not related to ACL GROUPS.

Single-context Mode Versus Multicontext Mode

tpinit() has two modes of operation: single-context mode and multicontext mode. In single-context mode, a process may join at most one application at any one time. Multiple application threads may access this application. Single-context mode is specified by calling tpinit() with a NULL parameter or by calling it without specifying the TPMULTICONTEXTS flag in the flags field of the TPINIT structure. Single-context mode is also specified when tpinit() is called implicitly by another ATMI function. The context state for a process operating in single-context mode is TPSINGLECONTEXT.

Note: The TPMULTICONTEXTS mode of tpinit will continue to work properly when the TMNOTHREADS environment variable is set to "yes".

In single-context mode, if tpinit() is called more than once (that is, if it is called after the client has already joined the application), no action is taken and success is returned

Multicontext mode is entered by calling tpinit() with the TPMULTICONTEXTS flag set in the flags field of the TPINIT structure. In multicontext mode, each call to tpinit() results in the creation of a separate application association.

An application association is a context that associates a process and a BEA Tuxedo ATMI application. A client may have associations with multiple BEA Tuxedo ATMI applications, and may also have multiple associations with the same application. All of a client's associations must be made to applications running the same release of the BEA Tuxedo ATMI system, and either all associations must be native clients or all associations must be Workstation clients

For native clients, the value of the TUXCONFIG environment variable is used to identify the application to which the new association will be made. For Workstation clients, the value of the WSNADDR OF WSENVFILE environment variable is used to identify the application to which the new association will be made. The context for the current thread is set to the new association.

In multicontext mode, the application can get a handle for the current context by calling tpgetctxt() and pass that handle as a parameter to tpsetctxt(), thus setting the context in which a particular thread or process will operate.

Mixing single-context mode and multicontext mode is not allowed. Once an application has chosen one of these modes, calling tpinit() in the other mode is not allowed unless tpterm() is first called for all application associations.

TPINFO Structure Field Descriptions

In addition to controlling multicontext and single-context modes, the setting of flags is used to indicate both the client-specific notification mechanism and the mode of system access. These two settings may override the application default. If these settings cannot override the application default, tpinit() prints a warning in a log file, ignores the setting, and restores the application default setting in the flags field upon return from tpinit(). For client notification, the possible values for flags are as follows:

TPU SIG

Select unsolicited notification by signals. This flag should be used only with single-threaded, single-contexted applications; it cannot be used when the TPMULTICONTEXTS flag is set.

TPU DIP

Select unsolicited notification by dip-in.

TPU THREAD

Select THREAD notification in a separate thread managed by the BEA Tuxedo ATMI system. This flag is allowed only on platforms that support multithreading. If TPU_THREAD is specified on a platform that does not

support multithreading, it is considered an invalid argument and will result in an error return with tperrno set to TPEINVAL.

TPU IGN

Ignore unsolicited notification.

Only one of the above flags can be used at a time. If the client does not select a notification method via the flags field, then the application default method will be set in the flags field upon return from tpinit().

For setting the mode of system access, the possible values for flags are as follows:

TPSA FASTPATH

Set system access to fastpath.

TPSA PROTECTED

Set system access to protected.

Only one of the above flags can be used at a time. If the client does not select a notification method or a system access mode via the flags field, then the application default method(s) will be set in the flags field upon return from tpinit(). See UBBCONFIG(5) for details on both client notification methods and system access modes.

If your application uses multithreading and/or multicontexting, you must set the following flag:

TPMULTICONTEXTS

See description in "Single-context Mode Versus Multicontext Mode."

datalen is the length of the application-specific data that follows. The buffer type switch entry for the TPINIT typed buffer sets this field based on the total size passed in for the typed buffer (the application data size is the total size less the size of the TPINIT structure itself plus the size of the data placeholder as defined in the structure). data is a place holder for variable length data that is forwarded to an application-defined authentication service. It is always the last element of this structure.

A macro, TPINITNEED, is available to determine the size TPINIT buffer necessary to accommodate a particular desired application specific data length. For example, if 8 bytes of application-specific data are desired, TPINITNEED(8) will return the required TPINIT buffer size.

A NULL value for tpinfo is allowed for applications not making use of the authentication feature of the BEA Tuxedo ATMI system. Clients using a NULL argument will get: defaults of 0-length strings for usrname, cltname and passwd; no flags set; and no application data.

Return Values

Upon failure, tpinit() leaves the calling process in its original context, returns -1, and sets tperrno to indicate the error condition. Also, tpurcode() is set to the value returned by the AUTHSVR(5) server.

Errors

Upon failure, tpinit() sets tperrno to one of the following values:

[TPEINVAL]

Invalid arguments were specified. tpinfo is non-NULL and does not point to a typed buffer of type TPINIT.

[TPENOENT]

The client cannot join the application because of space limitations.

[TPEPERM]

The client cannot join the application because it does not have permission to do so or because it has not supplied the correct application password. Permission may be denied based on an invalid application password, failure to pass application-specific authentication, or use of restricted names. tpurcode() may be set by an application-specific authentication server to explain why the client cannot join the application.

[TPEPROTO]

tpinit() has been called improperly. For example: (a) the caller is a server;

- (b) the TPMULTICONTEXTS flag has been specified in single-context mode; or
- (c) the ${\tt TPMULTICONTEXTS}$ flag has not been specified in multicontext mode.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

Interoperability

tpchkauth() and a non-NULL value for the TPINIT typed buffer argument of tpinit() are available only on sites running release 4.2 or later.

Portability

The interfaces described in tpinit(3c) are supported on UNIX system, Windows, and MS-DOS operating systems. However, signal-based notification is not supported on 16-bit Windows or MS-DOS platforms. If it is selected at tpinit() time, then a userlog() message is generated and the method is automatically set to dip-in.

Environment Variables

TUXCONFIG

Used within tpinit() when invoked by a native client. It indicates the application to which the client should connect. Note that this environment variable is referenced only when tpinit() is called. Subsequent calls make use of the application context.

WSENVETLE

Used within tpinit () when invoked by a Workstation client. It indicates a file containing environment variable settings that should be set in the caller's environment. See compilation (5) for details on environment variable settings necessary for Workstation clients. Note that this file is processed only when tpinit () is called and not before.

WSNADDR

Used within tpinit() when invoked by a Workstation client. It indicates the network addresses of the workstation listener that is to be contacted for access to the application. This variable is required for Workstation clients and is ignored for native clients.

TCP/IP addresses may be specified in the following forms:

```
//host.name:port_number
//#.#.#:#:port number
```

In the first format, the domain finds an address for hostname using the local name resolution facilities (usually DNS). hostname must be the local machine, and the local name resolution facilities must unambiguously resolve hostname to the address of the local machine.

In the second format, the string #.#.# is in dotted-decimal format. In dotted-decimal format, each # should be a number from 0 to 255. This dotted-decimal number represents the IP address of the local machine.

In both of the above formats, <code>port_number</code> is the TCP port number at which the domain process will listen for incoming requests. <code>port_number</code> can either be a number between 0 and 65535 or a name. If <code>port_number</code> is a name, then it must be found in the network services database on your local machine.

The address can also be specified in hexadecimal format when preceded by the characters 0x. Each character after the initial 0x is a number between 0 and 9 or a letter between A and F (case insensitive). The hexadecimal format is useful for arbitrary binary network addresses such as IPX/SPX or TCP/IP.

The address can also be specified as an arbitrary string. The value should be the same as that specified for the NLSADDR parameter in the NETWORK section of the configuration file.

More than one address can be specified if desired by specifying a comma-separated list of pathnames for WSNADDR. Addresses are tried in order until a connection is established. Any member of an address list can be specified as a parenthesized grouping of pipe-separated network addresses. For example:

WSNADDR=(//m1.acme.com:3050|//m2.acme.com:3050),//m3.acme.com:3050

For users running under Windows, the address string looks like the following:

set $WSNADDR = (//m1.acme.com:3050^{//m2.acme.com:3050}), //m3.acme.com:3050$

Because the pipe symbol (|) is considered a special character in Windows, it must be preceded by a carat (^)—an escape character in the Windows environment—when it is specified on the command line. However, if WSNADDR is defined in an envfile, the BEA Tuxedo ATMI system gets the values defined by WSNADDR through the tuxgetenv(3c) function. In this context, the pipe symbol (|) is not considered a special character, so you do not need to escape it with a carat (^).

The BEA Tuxedo ATMI system randomly selects one of the parenthesized addresses. This strategy distributes the load randomly across a set of listener processes. Addresses are tried in order until a connection is established. Use the value specified in the application configuration file for the workstation listener to be called. If the value begins with the characters 0x, it is interpreted as a string of hex-digits; otherwise, it is interpreted as ASCII characters.

WSFADDR

Used within tpinit() when invoked by a Workstation client. It specifies the network address used by the Workstation client when connecting to the workstation listener or workstation handler. This variable, along with the WSFRANGE variable, determines the range of TCP/IP ports to which a Workstation client will attempt to bind before making an outbound connection. This address must be a TCP/IP address. The port portion of the TCP/IP address represents the base address from which a range of TCP/IP

ports can be bound by the Workstation client. The WSFRANGE variable specifies the size of the range. For example, if this address is //mymachine.bea.com:30000 and WSFRANGE is 200, then all native processes attempting to make outbound connections from this *LMID* will bind a port on mymachine.bea.com between 30000 and 30200. If not set, this variable defaults to the empty string, which implies the operating system chooses a local port randomly.

WSFRANGE

Used within tpinit() when invoked by a Workstation client. It specifies the range of TCP/IP ports to which a Workstation client process will attempt to bind before making an outbound connection. The WSFADDR parameter specifies the base address of the range. For example, if the WSFADDR parameter is set to //mymachine.bea.com:30000 and WSFRANGE is set to 200, then all native processes attempting to make outbound connections from this LMID will bind a port on mymachine.bea.com between 30000 and 30200. The valid range is 1-65535. The default is 1.

WSDEVICE

Used within tpinit() when invoked by a Workstation client. It indicates the device name to be used to access the network. This variable is used by Workstation clients and ignored for native clients. Note that certain supported transport level network interfaces do not require a device name; for example, sockets and NetBIOS. Workstation clients supported by such interfaces need not specify WSDEVICE.

WSTYPE

Used within tpinit() when invoked by a Workstation client to negotiate encode/decode responsibilities with the native site. This variable is optional for Workstation clients and ignored for native clients.

WSRPLYMAX

Used by tpinit() to set the maximum amount of core memory that should be used for buffering application replies before they are dumped to file. The default for this parameter 256,000 bytes. For more information, see the programming documentation for your instantiation.

TMMINENCRYPTBITS

Used to establish the minimum level of encryption required to connect to the BEA Tuxedo ATMI system. "0" means no encryption, while "56" and "128" specify the encryption key length (in bits). The link-level encryption value of 40 bits is also provided for backward compatibility. If this minimum level of encryption cannot be met, link establishment will fail. The default is "0".

TMMAXENCRYPTBITS

Used to negotiate the level of encryption up to this level when connecting to the BEA Tuxedo ATMI system. "0" means no encryption, while "56" and "128" specify the encryption length (in bits). The link-level encryption value of 40 bits is also provided for backward compatibility. The default is "128."

Warning

Signal-based notification is not allowed in multicontext mode. In addition, signal restrictions may prevent the system from using signal-based notification even though it has been selected by a client. When this happens, the system generates a log message that it is switching notification for the selected client to dip-in and the client is notified then and thereafter via dip-in notification. (See the description of the NOTIFY parameter in the RESOURCES section of UBBCONFIG (5) for a detailed discussion of notification methods.)

Because signaling of clients is always done by the system, the behavior of notification is always consistent, regardless of where the originating notification call is made. Therefore to use signal-based notification:

- A native client must be running as an application administrator.
- A Workstation client is not required to be running as the application administrator

The ID for the application administrator is identified as part of the configuration for the application.

If signal-based notification is selected for a client, then certain ATMI calls may fail, returning TPGOTSIG due to receipt of an unsolicited message if TPSIGRSTRT is not specified.

See Also

Introduction to the C Language Application-to-Transaction Monitor Interface, tpgetctxt(3c), tpsetctxt(3c), tpterm(3c)

tpkey_close(3c)

Name tpkey close()—Closes a previously opened key handle.

Synopsis #include <atmi.h>

int tpkey close (TPKEY hKey, long flags)

Description

tpkey_close() releases a previously opened key handle and all resources associated with it. Any sensitive information, such as the principal's private key, is erased from memory.

Key handles can be opened in one of two ways:

- By an explicit call to tpkey open()
- As output from tpenvelope()

It is the application's responsibility to release key resources by calling <code>tpkey_close()</code>. Once a process closes a key, the process can no longer use the key handle to register a message buffer for digital signature or encryption. If the process opened the key using <code>tpkey_open()</code> with the <code>TPKEY_AUTOSIGN</code> or <code>TPKEY_AUTOENCRYPT</code> flag specified, the key handle no longer applies to future communication operations after the key is closed.

Even though a key is closed, however, the key handle continues to be valid for any associated signature or encryption request registered before the key was closed. When the last buffer associated with a closed key is freed or overwritten, resources attributable to the key are released.

On failure, this function returns -1 and sets tperrno to indicate the error condition.

The *flags* argument is reserved for future use and must be set to 0.

Return Values

Errors [TPEINVAL]

Invalid arguments were given. For example, the value of hKey is not a valid key.

[TPESYSTEM]

An error occurred. Consult the system error log file for details.

See Also tpenvelope(3c), tpkey_getinfo(3c), tpkey_open(3c), tpkey_setinfo(3c)

tpkey_getinfo(3c)

Name tpkey_getinfo()—Gets information associated with a key handle.

Synopsis #include <atmi.h>

int tpkey_getinfo(TPKEY hKey, char *attribute_name, void *value,
long *value len, long flags)

iong varue_ren, rong rrag

Description tpkey_getinfo() reports information about a key handle. A key handle represents a specific principal's key and the information associated with it.

The key under examination is identified by the hKey input parameter. The attribute for which information is desired is identified by the attribute_name input parameter. Some attributes are specific to a cryptographic service provider, but the following core set of attributes should be supported by all providers.

Attribute	Value	
PRINCIPAL	The name identifying the principal associated with the key (key handle), represented as a NULL-terminated character string.	
PKENCRYPT_ALG	An ASN.1 Distinguished Encoding Rules (DER) <i>object identifier</i> of the public key algorithm used by the key for public key encryption. The object identifier for RSA is identified in the following table, "Mapping of Algorithm Object Identifiers to Algorithms."	
PKENCRYPT_BITS	The key length of the public key algorithm (RSA modulus size). The value must be within the range of 512 to 2048 bits, inclusive.	
SIGNATURE_ALG	An ASN.1 DER <i>object identifier</i> of the digital signature algorithm used by the key for digital signature. The object identifiers for RSA and DSA are identified in the following table, "Mapping of Algorithm Object Identifiers to Algorithms."	
SIGNATURE_BITS	The key length of the digital signature algorithm (RSA modulus size). The value must be within the range of 512 to 2048 bits, inclusive.	
ENCRYPT_ALG	An ASN.1 DER <i>object identifier</i> of the symmetric key algorithm used by the key for bulk data encryption. The object identifiers for DES, 3DES, and RC2 are identified in the following table, "Mapping of Algorithm Object Identifiers to Algorithms."	

Attribute	Value
ENCRYPT_BITS	The key length of the symmetric key algorithm. The value must be within the range of 40 to 128 bits, inclusive.
	When an algorithm with a fixed key length is set in <code>ENCRYPT_ALG</code> , the <code>ENCRYPT_BITS</code> value is automatically set to the fixed key length. For example, if <code>ENCRYPT_ALG</code> is set to DES, the <code>ENCRYPT_BITS</code> value is automatically set to 56.
DIGEST_ALG	An ASN.1 DER <i>object identifier</i> of the message digest algorithm used by the key for digital signature.
	The object identifiers for MD5 and SHA-1 are identified in the following table, "Mapping of Algorithm Object Identifiers to Algorithms."
PROVIDER	The name of the cryptographic service provider.
VERSION	The version number of the cryptographic service provider's software.

The ASN.1 DER algorithm object identifiers supported by the default public key implementation are given in Table 11.

Table 11 Mapping of Algorithm Object Identifiers to Algorithms

ASN.1 DER Algorithm Object Identifier	Algorithm
$\{\ 0x06,\ 0x08,\ 0x2a,\ 0x86,\ 0x48,\ 0x86,\ 0xf7,\ 0x0d,\ 0x02,\ 0x05\ \}$	MD5
{ 0x06, 0x05, 0x2b, 0x0e, 0x03, 0x02, 0x1a }	SHA1
{ 0x06, 0x09, 0x2a, 0x86, 0x48, 0x86, 0xf7, 0x0d, 0x01, 0x01, 0x01 }	RSA
{ 0x06, 0x05, 0x2b, 0x0e, 0x03, 0x02, 0x0c }	DSA
{ 0x06, 0x05, 0x2b, 0x0e, 0x03, 0x02, 0x07 }	DES
{ 0x06, 0x08, 0x2a, 0x86, 0x48, 0x86, 0xf7, 0x0d, 0x03, 0x07 }	3DES
{ 0x06, 0x08, 0x2a, 0x86, 0x48, 0x86, 0xf7, 0x0d, 0x03, 0x02 }	RC2

The information associated with the specified <code>attribute_name</code> parameter will be stored in the memory location indicated by <code>value</code>. The maximum amount of data that can be stored at this location is specified by the caller in <code>value len</code>.

After tpkey_getinfo() completes, value_len is set to the size of the data actually returned (including a terminating NULL value for string values). If the number of bytes that need to be returned exceeds value_len, tpkey_getinfo() fails (with the TPELIMIT error code) and sets value_len to the required amount of space.

The *flags* argument is reserved for future use and must be set to 0.

Return Values On failure

On failure, this function returns -1 and sets tperrno to indicate the error condition.

Errors [TPEINVAL]

Invalid arguments were given. For example, hkey is not a valid key.

[TPESYSTEM]

An error occurred. Consult the system error log file for details.

[TPELIMIT]

Insufficient space was provided to hold the requested attribute value.

[TPENOENT]

The requested attribute is not associated with this key.

See Also tpkey close(3c), tpkey open(3c), tpkey setinfo(3c)

tpkey_open(3c)

Name tpkey_open()—Opens a key handle for digital signature generation, message

encryption, or message decryption.

Synopsis #include <atmi.h>

int tpkey_open(TPKEY *hKey, char *principal_name, char *location,
char *identity proof, long proof len, long flags)

Description

tpkey_open() makes a key handle available to the calling process. A key handle represents a specific principal's key and the information associated with it.

A key may be used for one or more of the following purposes:

Generating a digital signature, which protects a typed message buffer's content and proves that a specific principal originated the message. (A principal may be a person or a process.) This type of key is a private key and is available only to the key's owner.

Calling tpkey_open() with the principal's name and either the TPKEY_SIGNATURE or TPKEY_AUTOSIGN flag returns a handle to the principal's private key and digital certificate.

- Verifying a digital signature, which proves that a typed message buffer's content remains unaltered and that a specific principal originated the message.
 - Signature verification does not require a call to tpkey_open(); the verifying process uses the public key specified in the digital certificate accompanying the digitally signed message to verify the signature.
- Encrypting a message buffer destined for a specific principal. This type of key is available to any process with access to the principal's public key and digital certificate
 - Calling tpkey_open() with the principal's name and either the TPKEY_ENCRYPT or TPKEY_AUTOENCRYPT flag returns a handle to the principal's public key via the principal's digital certificate.
- Decrypting a message buffer intended for a specific principal. This type of key is a private key and is available only to the key's owner.
 - Calling tpkey_open() with the principal's name and the TPKEY_DECRYPT flag returns a handle to the principal's private key and digital certificate.

The key handle returned by tpkey_open() is stored in *hKey, the value of which cannot be NULL.

The <code>principal_name</code> input parameter specifies the key owner's identity. If the value of <code>principal_name</code> is a NULL pointer or an empty string, a default identity is assumed. The default identity may be based on the current login session, the current operating system account, or another attribute such as a local hardware device.

The file location of a key may be passed into the <code>location</code> parameter. If the underlying key management provider does not require a location parameter, the value of this parameter may be NULL.

To authenticate the identity of <code>principal_name</code>, proof material such as a password or pass phrase may be required. If required, the proof material should be referenced by <code>identity proof</code>. Otherwise, the value of this parameter may be NULL.

The length of the proof material (in bytes) is specified by proof_len. If proof_len is 0, identity proof is assumed to be a NULL-terminated character string.

The type of key access required for a key's mode of operation is specified by the *flags* parameter:

TPKEY SIGNATURE:

This private key is available to generate digital signatures.

TPKEY AUTOSIGN:

Whenever this process transmits a message buffer, the public key software uses the signer's private key to generate a digital signature and then attaches the digital signature to the buffer. TPKEY SIGNATURE is implied.

TPKEY ENCRYPT:

This public key is available to identify the recipient of an encrypted message.

TPKEY AUTOENCRYPT:

Whenever this process transmits a message buffer, the public key software encrypts the message content, uses the recipient's public key to generate an encryption envelope, and then attaches the encryption envelope to the buffer. TPKEY ENCRYPT is implied.

TPKEY DECRYPT:

This private key is available for decryption.

Any combination of one or more of these flag values is allowed. If a key is used only for encryption (TPKEY_ENCRYPT), identity_proof is not required and may be set to NULL.

Return Values

Upon successful completion, *hKey is set to a value that represents this key, for use by other functions such as tpsign() and tpseal().

On failure, this function returns -1 and sets tperrno to indicate the error condition.

Errors

[TPEINVAL]

Invalid arguments were given. For example, the value of hKey is NULL or the flags parameter is not set correctly.

[TPEPERM]

Permission failure. The cryptographic service provider was not able to access a private key for this principal, given the proof information and current environment.

[TPESYSTEM]

A system error occurred. Consult the systems error log file for details.

See Also

tpkey close(3c), tpkey getinfo(3c), tpkey setinfo(3c)

tpkey_setinfo(3c)

Name tpkey setinfo()—Sets optional attribute parameters associated with a key handle.

Synopsis #include <atmi.h>

int tpkey_setinfo(TPKEY hKey, char *attribute_name, void *value,
long value len, long flags)

Description tpkey_setinfo() sets an optional attribute parameter for a key handle. A key handle represents a specific principal's key and the information associated with it.

The key for which information is to be modified is identified by the <code>hKey</code> input parameter. The attribute for which information is to be modified is identified by the <code>attribute_name</code> input parameter. Some attributes may be specific to a certain cryptographic service provider, but the core set of attributes presented on the <code>tpkey_getinfo(3c)</code> reference page should be supported by all providers.

The information to be associated with the <code>attribute_name</code> parameter is stored in the memory location indicated by <code>value</code>. If the data content of <code>value</code> is self-describing, <code>value_len</code> is ignored (and may be 0). Otherwise, <code>value_len</code> must contain the length of data in <code>value</code>.

The *flags* argument is reserved for future use and must be set to 0.

Return Values On failure, this function returns -1 and sets tperrno to indicate the error condition.

Errors [TPEINVAL]

Invalid arguments were given. For example, hkey is not a valid key or attribute_name refers to a read-only value.

[TPELIMIT]

The value provided is too large.

[TPESYSTEM]

An error occurred. Consult the system error log file for details.

[TPENOENT]

The requested attribute is not recognized by the key's cryptographic service provider.

See Also tpkey_close(3c), tpkey_getinfo(3c), tpkey_open(3c)

tpnotify(3c)

Name tpnotify()—Routine for sending notification by client identifier.

Synopsis #include <atmi.h>

int tpnotify(CLIENTID *clientid, char *data, long len, long flags)

Description tpnotify() allows a client or server to send an unsolicited message to an individual client

clientid is a pointer to a client identifier saved from the TPSVCINFO structure of a previous or current service invocation, or passed to a client via some other communications mechanism (for example, retrieved via the administration interface).

The data portion of the request is pointed to by data, a buffer previously allocated by tpalloc(). Len specifies how much of data to send. Note that if data points to a buffer type that does not require a length to be specified, (for example, an FML fielded buffer) then Len is ignored (and may be 0). Also, data may be NULL in which case Len is ignored.

Upon successful return from $\mathtt{tpnotify}()$, the message has been delivered to the system for forwarding to the identified client. If the \mathtt{TPACK} flag was set, a successful return means the message has been received by the client. Furthermore, if the client has registered an unsolicited message handler, the handler will have been called.

The following is a list of valid flags:

TPACK

The request is sent and the caller blocks until an acknowledgement message is received from the target client.

TPNOBLOCK

The request is not sent if a blocking condition exists in sending the notification (for example, the internal buffers into which the message is transferred are full).

TPNOTIME

This flag signifies that the caller is willing to block indefinitely and wants to be immune to blocking timeouts. Transaction timeouts may still occur.

TPSIGRSTRT

If a signal interrupts any underlying system calls, then the interrupted system call is reissued.

Unless the TPACK flag is set, tpnotify() does not wait for the message to be delivered to the client.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpnotify().

Return Values

Upon failure, tpnotify() returns -1 and sets tperrno to indicate the error condition. If a call fails with a particular tperrno value, a subsequent call to tperrordetail(), with no intermediate ATMI calls, may provide more detailed information about the generated error. Refer to the tperrordetail(3c) reference page for more information

Errors Upon failure, tpnotify() sets tperrno to one of the following values:

[TPEINVAL]

Invalid arguments were given (for example, invalid flags).

[TPENOENT]

The target client does not exist or does not have an unsolicited handler set and the TPACK flag is set.

[TPETIME]

A blocking timeout occurred and neither TPNOBLOCK nor TPNOTIME were specified, or TPACK was set but no acknowledgment was received and TPNOTIME was not specified. (A blocking timeout cannot occur if TPNOBLOCK and/or TPNOTIME is specified.)

[TPEBLOCK]

A blocking condition was found on the call and TPNOBLOCK was specified.

[TPGOTSIG]

A signal was received and TPSIGRSTRT was not specified.

[TPEPROTO]

tpnotify() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

[TPERELEASE]

When the TPACK is set and the target is a client from a prior release of BEA Tuxedo that does not support the acknowledgment protocol.

See Also Introduction to the C Language Application-to-Transaction Monitor Interface, tpalloc(3c), tpbroadcast(3c), tpchkunsol(3c), tperrordetail(3c), tpinit(3c), tpsetunsol(3c), tpstrerrordetail(3c), tpterm(3c)

tpopen(3c)

Name tpopen ()—Routine for opening a resource manager.

Synopsis #include <atmi.h>
 int tpopen(void)

Description

tpopen() opens the resource manager to which the caller is linked. At most one resource manager can be linked to the caller. This function is used in place of resource manager-specific open() calls and allows a service routine to be free of calls that may hinder portability. Since resource managers differ in their initialization semantics, the specific information needed to open a particular resource manager is placed in a configuration file.

If a resource manager is already open (that is, tpopen() is called more than once), no action is taken and success is returned.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpopen().

Return Values

Upon failure, tpopen () returns -1 and sets tperrno to indicate the error condition.

Errors

Upon failure, tpopen() sets tperrno to one of the following values:

[TPERMERR]

A resource manager failed to open correctly. More information concerning the reason a resource manager failed to open can be obtained by interrogating a resource manager in its own specific manner. Note that any calls to determine the exact nature of the error hinder portability.

[TPEPROTO]

tpopen () was called in an improper context (for example, by a client that has not joined a BEA Tuxedo system server group).

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

See Also tpclose(3c)

tppost(3c)

Name tppost()—Posts an event.

Synopsis #include <atmi.h>

int tppost(char *eventname, char *data, long len, long flags)

Description

The caller uses tppost () to post an event and any accompanying data. The event is named by eventname and data, if not NULL, points to the data. The posted event and its data are dispatched by the BEA Tuxedo ATMI EventBroker to all subscribers whose subscriptions successfully evaluate against eventname and whose optional filter rules successfully evaluate against data.

eventname is a NULL-terminated string of at most 31 characters. eventname's first character cannot be a dot (".") as this character is reserved as the starting character for all events defined by the BEA Tuxedo ATMI system itself.

If data is non-NULL, it must point to a buffer previously allocated by tpalloc() and len should specify the amount of data in the buffer that should be posted with the event. Note that if data points to a buffer of a type that does not require a length to be specified (for example, an FML fielded buffer), then len is ignored. If data is NULL, len is ignored and the event is posted with no data.

When tppost() is used within a transaction, the transaction boundary can be extended to include those servers and/or stable-storage message queues notified by the EventBroker. When a transactional posting is made, some of the recipients of the event posting are notified on behalf of the poster's transaction (for example, servers and queues), while some are not (for example, clients).

If the poster is within a transaction and the TPNOTRAN flag is not set, the posted event goes to the EventBroker in transaction mode such that it dispatches the event as part of the poster's transaction. The broker dispatches transactional event notifications only to those service routine and stable-storage queue subscriptions that used the TPEVTRAN bit setting in the ctl->flags parameter passed to tpsubscribe(). Client notifications, and those service routine and stable-storage queue subscriptions that did not use the TPEVTRAN bit setting in the ctl->flags parameter passed to tpsubscribe(), are also dispatched by the EventBroker but not as part of the posting process's transaction.

If the poster is outside a transaction, tppost() is a one-way post with no acknowledgement when the service associated with the event fails. This occurs even when TPEVTRAN is set for that event (using the ctl->flags parameter passed to tpsubscribe()). If the poster is in a transaction, then tppost() returns TPESVCFAIL when the associated service fails in the event.

The following is a list of valid flags:

TPNOTRAN

If the caller is in transaction mode and this flag is set, then the event posting is not made on behalf of the caller's transaction. A caller in transaction mode that sets this flag is still subject to the transaction timeout (and no other) when posting events. If the event posting fails, the caller's transaction is not affected

TPNOREPLY

Informs tppost() not to wait for the EventBroker to process all subscriptions for eventname before returning. When TPNOREPLY is set, tpurcode() is set to zero regardless of whether tppost() returns successfully or not. When the caller is in transaction mode, this setting cannot be used unless TPNOTRAN is also set.

TPNOBLOCK

The event is not posted if a blocking condition exists. If such a condition occurs, the call fails and tperrno is set to TPEBLOCK. When TPNOBLOCK is not specified and a blocking condition exists, the caller blocks until the condition subsides or a timeout occurs (either transaction or blocking timeout).

TPNOTIME

This flag signifies that the caller is willing to block indefinitely and wants to be immune to blocking timeouts. Transaction timeouts may still occur.

TPSIGRSTRT

If a signal interrupts any underlying system calls, then the interrupted system call is reissued. When TPSIGRSTRT is not specified and a signal interrupts a system call, then tppost() fails and tperrno is set to TPGOTSIG.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tppost().

Return Values

Upon successful return from tppost(), tpurcode() contains the number of event notifications dispatched by the EventBroker on behalf of eventname (that is, postings for those subscriptions whose event expression evaluated successfully against eventname and whose filter rule evaluated successfully against data). Upon return where tperrno is set to TPESVCFAIL, tpurcode() contains the number of non-transactional event notifications dispatched by the EventBroker on behalf of eventname.

Upon failure, tppost () returns -1 sets tperrno to indicate the error condition.

Errors

Upon failure, tppost() sets tperrno to one of the following values. (Unless otherwise noted, failure does not affect the caller's transaction, if one exists.)

[TPEINVAL]

Invalid arguments were given (for example, eventname is NULL).

[TPENOENT]

Cannot access the BEA Tuxedo User EventBroker.

[TPETRAN]

The caller is in transaction mode, TPNOTRAN was not set and tppost() contacted an EventBroker that does not support transaction propagation (that is, TMUSREVT (5) is not running in a BEA Tuxedo ATMI system group that supports transactions).

[TPETIME]

This error code indicates that either a timeout has occurred or tppost() has been attempted, in spite of the fact that the current transaction is already marked rollback only.

If the caller is in transaction mode, then either the transaction is already rollback only or a transaction timeout has occurred. The transaction is marked abort-only. If the caller is not in transaction mode, a blocking timeout has occurred. (A blocking timeout cannot occur if TPNOBLOCK and/or TPNOTIME is specified.)

If a transaction timeout has occurred, then, with one exception, any attempts to send new requests or receive outstanding replies will fail with TPETIME until the transaction has been aborted. The exception is a request that does not block, expects no reply, and is not sent on behalf of the caller's transaction (that is, tpacall() with TPNOTRAN, TPNOBLOCK, and TPNOREPLY set).

When tppost() fails inside a transaction, the transaction is put into the TX_ROLLBACK_ONLY state. This state is treated, for most purposes, as though

it were equivalent to a timeout. All further ATMI calls for this transaction (with the exception of those issued in the circumstances described in the previous paragraph) will fail with TPETIME.

[TPESVCFAIL]

The EventBroker encountered an error posting a transactional event to either a service routine or to a stable storage queue on behalf of the caller's transaction. The caller's current transaction is marked abort-only. When this error is returned, tpurcode() contains the number of non-transactional event notifications dispatched by the EventBroker on behalf of eventname; transactional postings are not counted since their effects will be aborted upon completion of the transaction. Note that so long as the transaction has not timed out, further communication may be performed before aborting the transaction and that any work performed on behalf of the caller's transaction will be aborted upon transaction completion (that is, for subsequent communication to have any lasting effect, it should be done with TPNOTRAN set).

[TPEBLOCK]

A blocking condition exists and TPNOBLOCK was specified.

[TPGOTSIG]

A signal was received and TPSIGRSTRT was not specified.

[TPEPROTO]

tppost() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

tprealloc(3c)

Name tprealloc()—Routine to change the size of a typed buffer.

Description

tprealloc() changes the size of the buffer pointed to by ptr to size bytes and returns a pointer to the new (possibly moved) buffer. Similar to tpalloc(), the size of the buffer will be at least as large as the larger of size and dfltsize, where dfltsize is the default buffer size specified in tmtype_sw. If the larger of the two is less than or equal to zero, then the buffer is unchanged and NULL is returned. A buffer's type remains the same after it is reallocated. After this function returns successfully, the returned pointer should be used to reference the buffer; ptr should no longer be used. The buffer's contents will not change up to the lesser of the new and old sizes.

Some buffer types require initialization before they can be used. tprealloc() reinitializes a buffer (in a communication manager-specific manner) after it is reallocated and before it is returned. Thus, the buffer returned to the caller is ready for use.

A thread in a multithreaded application may issue a call to tprealloc() while running in any context state, including TPINVALIDCONTEXT.

Return Values

Upon successful completion, tprealloc() returns a pointer to a buffer of the appropriate type aligned on a long word.

Upon failure, tprealloc() returns NULL and sets tperrno to indicate the error condition.

Errors

If the reinitialization function fails, tprealloc() fails, returning NULL and the contents of the buffer pointed to by ptr may not be valid. Upon failure, tprealloc() sets tperrno to one of the following values:

[TPEINVAL]

Invalid arguments were given (for example, ptr does not point to a buffer originally allocated by tpalloc()).

[TPEPROTO]

tprealloc() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

Usage If buffer reinitialization fails, tprealloc() fails returning NULL and the contents of the buffer pointed to by ptr may not be valid. This function should not be used in concert with malloc(), realloc() or free() in the C library (for example, a buffer allocated with tprealloc() should not be freed with free()).

See Also tpalloc(3c), tpfree(3c), tptypes(3c)

tprecv(3c)

Name tprecy()—Routine for receiving a message in a conversational connection.

Synopsis #include <atmi.h>

int tprecv(int cd, char **data, long *len, long flags, long \
 *revent)

Description

tprecv() is used to receive data sent across an open connection from another program. tprecv() 's first argument, cd, specifies on which open connection to receive data. cd is a descriptor returned from either tpconnect() or the TPSVCINFO parameter to the service. The second argument, data, is the address of a pointer to a buffer previously allocated by tpalloc().

data must be the address of a pointer to a buffer previously allocated by tpalloc() and len should point to a long that tprecv() sets to the amount of data successfully received. Upon successful return, *data points to a buffer containing the reply and *len contains the size of the buffer. FML and FML32 buffers often assume a minimum size of 4096 bytes; if the reply is larger than 4096 bytes, the size of the buffer is increased to a size large enough to accommodate the data being returned.

Buffers on the sending side that may be only partially filled (for example, FML or STRING buffers) will have only the amount that is used sent. The system may then enlarge the received data size by some arbitrary amount. This means that the receiver may receive a buffer that is smaller than what was originally allocated by the sender, yet larger than the data that was sent.

The receive buffer may grow, or it may shrink, and its address almost invariably changes, as the system swaps buffers around internally. To determine whether (and how much) a reply buffer changed in size, compare its total size before tprecv() was issued with *len. See "Introduction to the C Language Application-to-Transaction Monitor Interface" for more information about buffer management.

If *len is 0, then no data was received and neither *data nor the buffer it points to were modified. It is an error for data, *data or len to be NULL.

tprecv() can be issued only by the program that does not have control of the connection.

The following is a list of valid flags:

TPNOCHANGE

By default, if a buffer is received that differs in type from the buffer pointed to by *data, then *data's buffer type changes to the received buffer's type

so long as the receiver recognizes the incoming buffer type. When this flag is set, the type of the buffer pointed to by *data is not allowed to change. That is, the type and subtype of the received buffer must match the type and subtype of the buffer pointed to by *data.

TPNOBLOCK

tprecv() does not wait for data to arrive. If data is already available to receive, then tprecv() gets the data and returns. When this flag is not specified and no data is available to receive, the caller blocks until data arrives

TPNOTIME

This flag signifies that the caller is willing to block indefinitely and wants to be immune to blocking timeouts. Transaction timeouts will still affect the program.

TPSIGRSTRT

If a signal interrupts the underlying receive system call, then the call is reissued.

If an event exists for the descriptor, <code>cd</code>, then <code>tprecv()</code> will return setting <code>tperrno</code> to <code>TPEEVENT</code>. The event type is returned in <code>revent</code>. Data can be received along with the <code>TPEV_SVCSUCC</code>, <code>TPEV_SVCFAIL</code>, and <code>TPEV_SENDONLY</code> events. Valid events for <code>tprecv()</code> are as follows:

TPEV DISCONIMM

Received by the subordinate of a conversation, this event indicates that the originator of the conversation has either issued an immediate disconnect on the connection via tpdiscon(), or it issued tpreturn(), tpcommit() or tpabort() with the connection still open. This event is also returned to the originator or subordinate when a connection is broken due to a communications error (for example, a server, machine, or network failure). Because this is an immediate disconnection notification (that is, abortive rather than orderly), data in transit may be lost. If the two programs were participating in the same transaction, then the transaction is marked abort-only. The descriptor used for the connection is no longer valid.

TPEV SENDONLY

The program on the other end of the connection has relinquished control of the connection. The recipient of this event is allowed to send data but cannot receive any data until it relinquishes control.

TPEV SVCERR

Received by the originator of a conversation, this event indicates that the subordinate of the conversation has issued tpreturn().tpreturn()

encountered an error that precluded the service from returning successfully. For example, bad arguments may have been passed to tpreturn() or tpreturn() may have been called while the service had open connections to other subordinates. Due to the nature of this event, any application defined data or return code are not available. The connection has been torn down and is no longer a valid descriptor. If this event occurred as part of the cd recipient's transaction, then the transaction is marked abort-only.

TPEV SVCFAIL

Received by the originator of a conversation, this event indicates that the subordinate service on the other end of the conversation has finished unsuccessfully as defined by the application (that is, it called tpreturn() with TPFAIL or TPEXIT). If the subordinate service was in control of this connection when tpreturn() was called, then it can pass an application defined return value and a typed buffer back to the originator of the connection. As part of ending the service routine, the server has torn down the connection. Thus, cd is no longer a valid descriptor. If this event occurred as part of the recipient's transaction, then the transaction is marked abort-only.

TPEV SVCSUCC

Received by the originator of a conversation, this event indicates that the subordinate service on the other end of the conversation has finished successfully as defined by the application (that is, it called tpreturn() with TPSUCCESS). As part of ending the service routine, the server has torn down the connection. Thus, cd is no longer a valid descriptor. If the recipient is in transaction mode, then it can either commit (if it is also the initiator) or abort the transaction causing the work done by the server (if also in transaction mode) to either commit or abort.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tprecv().

Return Values

Upon return from tprecv() where revent is set to either TPEV_SVCSUCC or TPEV_SVCFAIL, the tpurcode global contains an application defined value that was sent as part of tpreturn().

Upon failure, tprecv() returns -1 and sets tperrno to indicate the error condition. If a call fails with a particular tperrno value, a subsequent call to tperrordetail(), with no intermediate ATMI calls, may provide more detailed information about the generated error. Refer to the tperrordetail(3c) reference page for more information.

Errors Upon failure, tprecv() sets tperrno to one of the following values:

[TPEINVAL]

Invalid arguments were given (for example, data is not the address of a pointer to a buffer allocated by tpalloc() or flags are invalid).

[TPEOTYPE]

Either the type and subtype of the incoming buffer are not known to the caller, or TPNOCHANGE was set in flags and the type and subtype of *data do not match the type and subtype of the incoming buffer. Regardless, neither *data, its contents nor *len are changed. If the conversation is part of the caller's current transaction, then the transaction is marked abort-only because the incoming buffer is discarded.

[TPEBADDESC]

cd is invalid.

[TPETIME]

This error code indicates that either a timeout has occurred or tprecv() has been attempted, in spite of the fact that the current transaction is already marked rollback only.

If the caller is in transaction mode, then either the transaction is already rollback only or a transaction timeout has occurred. The transaction is marked abort-only. If the caller is not in transaction mode, a blocking timeout has occurred. (A blocking timeout cannot occur if TPNOBLOCK and/or TPNOTIME is specified.) In either case, no changes are made to *data or its contents.

If a transaction timeout has occurred, then, with one exception, any attempts to send new requests or receive outstanding replies will fail with TPETIME until the transaction has been aborted. The exception is a request that does not block, expects no reply, and is not sent on behalf of the caller's transaction (that is, tpacall() with TPNOTRAN, TPNOBLOCK, and TPNOREPLY set).

When an ATMI call fails inside a transaction, the transaction is put into the <code>TX_ROLLBACK_ONLY</code> state. This state is treated, for most purposes, as though it were equivalent to a timeout. All further ATMI calls for this transaction (with the exception of those issued in the circumstances described in the previous paragraph) will fail with <code>TPETIME</code>.

[TPEEVENT]

An event occurred and its type is available in revent. There is a relationship between the [TPETIME] and the [TPEEVENT] return codes. While in transaction mode, if the receiving side of a conversation is blocked on tprecv and the sending side calls tpabort(), then the receiving side gets a return

code of [TPEVENT] with an event of TPEV_DISCONIMM. If, however, the sending side calls tpabort() before the receiving side calls tprecv(), then the transaction may have already been removed from the GTT, which causes tprecv() to fail with the [TPETIME] code.

[TPEBLOCK]

A blocking condition exists and TPNOBLOCK was specified.

[TPGOTSIG]

A signal was received and TPSIGRSTRT was not specified.

[TPEPROTO]

tprecv() was called in an improper context (for example, the connection was established such that the calling program can only send data).

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

Usage

A server can pass an application defined return value and typed buffer when calling tpreturn(). The return value is available in the global variable tpurcode and the buffer is available in data

See Also

```
tpalloc(3c), tpconnect(3c), tpdiscon(3c), tperrordetail(3c),
tpsend(3c), tpservice(3c), tpstrerrordetail(3c)
```

tpresume(3c)

Name tpresume()—Resumes a global transaction.

Synopsis #include <atmi.h>

int tpresume(TPTRANID *tranid, long flags)

Description tpresume () is used to resume work on behalf of a previously suspended transaction.

Once the caller resumes work on a transaction, it must either suspend it with

tpsuspend(), or complete it with one of tpcommit() or tpabort() at a later time.

The caller must ensure that its linked resource managers have been opened (via tpopen()) before it can resume work on any transaction.

tpresume () places the caller in transaction mode on behalf of the global transaction identifier pointed to by tranid. It is an error for tranid to be NULL.

Currently, *flags* are reserved for future use and must be set to 0.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpresume ().

Return Value

tpresume () returns -1 on error and sets tperrno to indicate the error condition.

Errors

Under the following conditions, tpresume () fails and sets tperrno to:

[TPEINVAL]

Either tranid is a NULL pointer, it points to a non-existent transaction identifier (including previously completed or timed-out transactions), or it points to a transaction identifier that the caller is not allowed to resume. The caller's state with respect to the transaction is not changed.

[TPEMATCH]

tranid points to a transaction identifier that another process has already resumed. The caller's state with respect to the transaction is not changed.

[TPETRAN]

The BEA Tuxedo system is unable to resume the global transaction because the caller is currently participating in work outside any global transaction with one or more resource managers. All such work must be completed before a global transaction can be resumed. The caller's state with respect to the local transaction is unchanged.

[TPEPROTO]

tpresume () was called in an improper context (for example, the caller is already in transaction mode). The caller's state with respect to the transaction is not changed.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

Notes XA-compliant resource managers must be successfully opened to be included in the global transaction. (See tpopen (3c) for details.)

A process resuming a suspended transaction must reside on the same logical machine (LMID) as the process that suspended the transaction. For a Workstation client, the workstation handler (WSH) to which it is connected must reside on the same logical machine as the handler for the Workstation client that suspended the transaction.

See Also tpabort (3c), tpcommit (3c), tpopen (3c), tpsuspend (3c)

tpreturn(3c)

Name tpreturn ()—Returns from a BEA Tuxedo ATMI system service routine.

Synopsis void tpreturn(int rval, long rcode, char *data, long len, long \ flags)

Description

tpreturn() indicates that a service routine has completed. tpreturn() acts like a return statement in the C language (that is, when tpreturn() is called, the service routine returns to the BEA Tuxedo ATMI system dispatcher). It is recommended that tpreturn() be called from within the service routine dispatched to ensure correct return of control to the BEA Tuxedo ATMI system dispatcher.

tpreturn() is used to send a service's reply message. If the program receiving the reply is waiting in either tpcall(), tpgetrply(), or tprecv(), then after a successful call to tpreturn(), the reply is available in the receiver's buffer.

For conversational services, tpreturn() also tears down the connection. That is, the service routine cannot call tpdiscon() directly. To ensure correct results, the program that connected to the conversational service should not call tpdiscon(); rather, it should wait for notification that the conversational service has completed (that is, it should wait for one of the events, like TPEV_SVCSUCC or TPEV_SVCFAIL, sent by tpreturn()).

If the service routine was in transaction mode, <code>tpreturn()</code> places the service's portion of the transaction in a state from which it may be either committed or rolled back when the transaction is completed. A service may be invoked multiple times as part of the same transaction so it is not necessarily fully committed or rolled back until either <code>tpcommit()</code> or <code>tpabort()</code> is called by the originator of the transaction.

tpreturn() should be called after receiving all replies expected from service requests initiated by the service routine. Otherwise, depending on the nature of the service, either a TPESVCERR status or a TPEV_SVCERR event will be returned to the program that initiated communication with the service routine. Any outstanding replies that are not received will automatically be dropped by the communication manager. In addition, the descriptors for those replies become invalid.

tpreturn() should be called after closing all connections initiated by the service. Otherwise, depending on the nature of the service, either a TPESVCERR or a TPEV_SVCERR event will be returned to the program that initiated communication with the service routine. Also, an immediate disconnect event (that is, TPEV_DISCONIMM) is sent over all open connections to subordinates.

Since a conversational service has only one open connection which it did not initiate, the communication manager knows over which descriptor data (and any event) should be sent. For this reason, a descriptor is not passed to tpreturn().

The following is a description of the arguments for tpreturn (). rval can be set to one of the following:

TPSUCCESS

The service has terminated successfully. If data is present, then it will be sent (barring any failures processing the return). If the caller is in transaction mode, then tpreturn() places the caller's portion of the transaction in a state such that it can be committed when the transaction ultimately commits. Note that a call to tpreturn() does not necessarily finalize an entire transaction. Also, even though the caller indicates success, if there are any outstanding replies or open connections, if any work done within the service caused its transaction to be marked rollback-only, then a failed message is sent (that is, the recipient of the reply receives a TPESVCERR indication or a TPEV_SVCERR event). Note that if a transaction becomes rollback-only while in the service routine for any reason, then rval should be set to TPFAIL. If TPSUCCESS is specified for a conversational service, a TPEV_SVCSUCC event is generated.

TPFAIL

The service has terminated unsuccessfully from an application standpoint. An error will be reported to the program receiving the reply. That is, the call to get the reply will fail and the recipient receives a TPSVCFAIL indication or a TPEV_SVCFAIL event. If the caller is in transaction mode, then tpreturn() marks the transaction as rollback-only (note that the transaction may already be marked rollback-only). Barring any failures in processing the return, the caller's data is sent, if present. One reason for not sending the caller's data is that a transaction timeout has occurred. In this case, the program waiting for the reply will receive an error of TPETIME. If TPFAIL is specified for a conversational service, a TPEV_SVCFAIL event is generated.

TPEXIT

This value behaves the same as TPFAIL with respect to completing the service, but when TPEXIT is returned, the server exits after the transaction is rolled back and the reply is sent back to the requester.

When specified for a multithreaded process, TPEXIT indicates that an entire process (not only a single thread within that process) will be killed. If the server is restartable, then the server is restarted automatically.

If rval is not set to one of these three values, then it defaults to TPFAIL.

An application defined return code, rcode, may be sent to the program receiving the service reply. This code is sent regardless of the setting of rval as long as a reply can be successfully sent (that is, as long as the receiving call returns success or TPESVCFAIL). In addition, for conversational services, this code can be sent only if the service routine has control of the connection when it issues tpreturn(). The value of rcode is available in the receiver in the variable, tpurcode().

data points to the data portion of a reply to be sent. If data is non-NULL, it must point to a buffer previously obtained by a call to tpalloc(). If this is the same buffer passed to the service routine upon its invocation, then its disposition is up to the BEA Tuxedo ATMI system dispatcher; the service routine writer does not have to worry about whether it is freed or not. In fact, any attempt by the user to free this buffer will fail. However, if the buffer passed to tpreturn() is not the same one with which the service is invoked, then tpreturn() frees that buffer. Although the main buffer is freed, any buffers referenced by embedded fields within that buffer are not freed. len specifies the amount of the data buffer to be sent. If data points to a buffer which does not require a length to be specified, (for example, an FML fielded buffer), then len is ignored (and can be 0).

If data is NULL, then len is ignored. In this case, if a reply is expected by the program that invoked the service, then a reply is sent with no data. If no reply is expected, then tpreturn() frees data as necessary and returns sending no reply.

Currently, flags is reserved for future use and must be set to 0 (if set to a non-zero value, the recipient of the reply receives a TPESVCERR indication or a TPEV_SVCERR event).

If the service is conversational, there are two cases where the caller's return code and the data portion are not transmitted:

- If the connection has already been torn down when the call is made (that is, the caller has received TPEV_DISCONIMM on the connection), then this call simply ends the service routine and rolls back the current transaction, if one exists.
- If the caller does not have control of the connection, either TPEV_SVCFAIL or TPEV_SVCERR is sent to the originator of the connection as described above. Regardless of which event the originator receives, no data is transmitted; however, if the originator receives the TPEV_SVCFAIL event, the return code is available in the originator's tpurcode() variable.

Return Values

A service routine does not return any value to its caller, the BEA Tuxedo ATMI system dispatcher; thus, it is declared as a void. Service routines, however, are expected to terminate using either tpreturn () or tpforward(). A conversational service routine

must use tpreturn(), and cannot use tpforward(). If a service routine returns without using either tpreturn() or tpforward() (that is, it uses the C language return statement or just simply "falls out of the function") or tpforward() is called from a conversational server, the server will print a warning message in the log and return a service error to the service requester. In addition, all open connections to subordinates will be disconnected immediately, and any outstanding asynchronous replies will be dropped. If the server was in transaction mode at the time of failure, the transaction is marked rollback-only. Note also that if either tpreturn() or tpforward() are used outside of a service routine (for example, in clients, or in tpsvrinit() or tpsvrdone()), then these routines simply return having no effect.

Errors

Since tpreturn() ends the service routine, any errors encountered either in handling arguments or in processing cannot be indicated to the function's caller. Such errors cause tperrno to be set to TPESVCERR for a program receiving the service's outcome via either tpcall() or tpgetrply(), and cause the event, TPEV_SVCERR, to be sent over the conversation to a program using tpsend() or tprecv().

If either SVCTIMEOUT in the UBBCONFIG file or TA_SVCTIMEOUT in the TM_MIB is non-zero, the event TPEV SVCERR is returned when a service timeout occurs.

tperrordetail() and tpstrerrordetail() can be used to get additional information about an error produced by the last BEA Tuxedo ATMI system routine called in the current thread. If an error occurred, tperrordetail() returns a numeric value that can be used as an argument to trstrerrordetail() to retrieve the text of the error detail.

See Also

tpalloc(3c), tpcall(3c), tpconnect(3c), tpforward(3c), tprecv(3c),
tpsend(3c), tpservice(3c)

tpscmt(3c)

Name tpscmt()—Routine for setting when tpcommit() should return.

Synopsis #include <atmi.h>
 int tpscmt(long flags)

Description

tpscmt() sets the TP_COMMIT_CONTROL characteristic to the value specified in flags. The TP_COMMIT_CONTROL characteristic affects the way tpcommit() behaves with respect to returning control to its caller. A program can call tpscmt() regardless of whether it is in transaction mode or not. Note that if the caller is participating in a transaction that another program must commit, then its call to tpscmt() does not affect that transaction. Rather, it affects subsequent transactions that the caller will commit.

In most cases, a transaction is committed only when a BEA Tuxedo ATMI system thread of control calls <code>tpcommit()</code>. There is one exception: when a service is dispatched in transaction mode because the <code>AUTOTRAN</code> variable in the *SERVICES section of the <code>UBBCONFIG</code> file is enabled, then the transaction completes upon calling <code>tpreturn()</code>. If <code>tpforward()</code> is called, then the transaction will be completed by the server ultimately calling <code>tpreturn()</code>. Thus, the setting of the <code>TP_COMMIT_CONTROL</code> characteristic in the service that calls <code>tpreturn()</code> determines when <code>tpcommit()</code> returns control within a server. If <code>tpcommit()</code> returns a heuristic error code, the server will write a message to a log file.

When a client joins a BEA Tuxedo ATMI system application, the initial setting for this characteristic comes from a configuration file. (See the CMTRET variable in the RESOURCES section of UBBCONFIG (5))

The following are the valid settings for *flags*:

TP CMT LOGGED

This flag indicates that <code>tpcommit()</code> should return after the commit decision has been logged by the first phase of the two-phase commit protocol but before the second phase has completed. This setting allows for faster response to the caller of <code>tpcommit()</code> although there is a risk that a transaction participant might decide to heuristically complete (that is, abort) its work due to timing delays waiting for the second phase to complete. If this occurs, there is no way to indicate this situation to the caller <code>sincetpcommit()</code> has already returned (although the BEA Tuxedo ATMI system writes a message to a log file when a resource manager takes a heuristic decision). Under normal conditions, participants that promise to commit during the first phase will do so during the second phase. Typically, problems caused by network or site

failures are the sources for heuristic decisions being made during the second phase.

TP_CMT_COMPLETE

This flag indicates that tpcommit (3c) should return after the two-phase commit protocol has finished completely. This setting allows for tpcommit() to return an indication that a heuristic decision occurred during the second phase of commit.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpscmt().

Return Values

Upon success, tpscmt() returns the previous value of the TP_COMMIT_CONTROL characteristic.

Upon failure, tpscmt() returns -1 and sets tperrno to indicate the error condition.

Errors Upon failure, tpscmt() sets tperrno to one of the following values:

[TPEINVAL]

flags is not one of TP CMT LOGGED or TP CMT COMPLETE.

[TPEPROTO]

tpscmt() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

Notices

When using <code>tpbegin()</code>, <code>tpcommit()</code> and <code>tpabort()</code> to delineate a BEA Tuxedo ATMI system transaction, it is important to remember that only the work done by a resource manager that meets the XA interface (and is linked to the caller appropriately) has transactional properties. All other operations performed in a transaction are not affected by either <code>tpcommit()</code> or <code>tpabort()</code>. See <code>buildserver(1)</code> for details on

Introduction to the C Language Application-to-Transaction Monitor Interface

linking resource managers that meet the XA interface into a server such that operations performed by that resource manager are part of a BEA Tuxedo ATMI system transaction.

See Also tpabort(3c), tpbegin(3c), tpcommit(3c), tpgetlev(3c)

tpseal(3c)

Name tpseal()—Marks a typed message buffer for encryption.

Synopsis #include <atmi.h>

int tpseal (char *data, TPKEY hKey, long flags)

Description

tpseal() marks, or registers, a message buffer for encryption. The principal who owns hKey can decrypt this buffer and access its content. A buffer may be sealed for more than one recipient principal by making several calls to tpseal().

data must point to a valid typed message buffer either (1) previously allocated by a process calling tpalloc() or (2) delivered by the system to a receiving process. The content of the buffer may be modified after tpseal() is invoked.

When the message buffer pointed to by data is transmitted from a process, the public key software encrypts the message content and attaches an encryption envelope to the message buffer for each encryption registration request. An encryption envelope enables a receiving process to decrypt the message.

The *flags* argument is reserved for future use and must be set to 0.

Return Values

On failure, this function returns -1 and sets tperrno to indicate the error condition.

Errors

[TPEINVAL]

Invalid arguments were given. For example, hkey is not a valid key for encrypting or data is NULL.

[TPESYSTEM]

An error has occurred. Consult the system error log file for details.

See Also

tpkey close(3c), tpkey open(3c)

tpsend(3c)

Name tpsend()—Routine for sending a message in a conversational connection.

Synopsis #include <atmi.h>

int tpsend(int cd, char *data, long len, long flags, long *revent)

Description

tpsend() is used to send data across an open connection to another program. The caller must have control of the connection. tpsend()'s first argument, cd, specifies the open connection over which data is sent. cd is a descriptor returned from either tpconnect() or the TPSVCINFO parameter passed to a conversational service.

The second argument, data, must point to a buffer previously allocated by tpalloc(). Len specifies how much of the buffer to send. Note that if data points to a buffer of a type that does not require a length to be specified (for example, an FML fielded buffer), then Len is ignored (and may be 0). Also, data can be NULL in which case Len is ignored (no application data is sent—this might be done, for instance, to grant control of the connection without transmitting any data). The type and subtype of data must match one of the types and subtypes recognized by the other end of the connection.

The following is a list of valid flags:

TPRECVONLY

This flag signifies that, after the caller's data is sent, the caller gives up control of the connection (that is, the caller can not issue any more tpsend() calls). When the receiver on the other end of the connection receives the data sent by tpsend(), it will also receive an event (TPEV_SENDONLY) indicating that it has control of the connection (and can not issue more any tprecv() calls).

TPNOBLOCK

The data and any events are not sent if a blocking condition exists (for example, the internal buffers into which the message is transferred are full). When TPNOBLOCK is not specified and a blocking condition exists, the caller blocks until the condition subsides or a timeout occurs (either transaction or blocking timeout).

TPNOTIME

This flag signifies that the caller is willing to block indefinitely and wants to be immune to blocking timeouts. Transaction timeouts may still occur.

TPSIGRSTRT

If a signal interrupts any underlying system calls, then the interrupted system call is reissued

If an event exists for the descriptor, cd, then tpsend() will fail without sending the caller's data. The event type is returned in revent. Valid events for tpsend() are as follows:

TPEV DISCONIMM

Received by the subordinate of a conversation, this event indicates that the originator of the conversation has issued an immediate disconnect on the connection via tpdiscon(), or it issued tpreturn(), tpcommit() or tpabort() with the connection still open. This event is also returned to the originator or subordinate when a connection is broken due to a communications error (for example, a server, machine, or network failure).

TPEV SVCERR

Received by the originator of a conversation, this event indicates that the subordinate of the conversation has issued tpreturn() without having control of the conversation. In addition, tpreturn() has been issued in a manner different from that described for TPEV_SVCFAIL below. This event can be caused by an ACL permissions violation; that is, the originator does not have permission to connect to the receiving process. This event is not returned at the time the tpconnect() is issued, but is returned with the first tpsend() (following a tpconnect() with flag TPSENDONLY) or tprecv() (following a tpconnect() with flag TPRECVONLY). A system event and a log message are also generated.

TPEV SVCFAIL

Received by the originator of a conversation, this event indicates that the subordinate of the conversation has issued tpreturn() without having control of the conversation. In addition, tpreturn() was issued with the rval set to TPFAIL or TPEXIT and data to NULL.

Because each of these events indicates an immediate disconnection notification (that is, abortive rather than orderly), data in transit may be lost. The descriptor used for the connection is no longer valid. If the two programs were participating in the same transaction, then the transaction has been marked abort-only.

If the value of either SVCTIMEOUT in the UBBCONFIG file or TA_SVCTIMEOUT in the TM MIB is non-zero, TPESVCERR is returned when a service timeout occurs.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpsend().

Introduction to the C Language Application-to-Transaction Monitor Interface

Return Values

Upon return from tpsend() where revent is set to either TPEV_SVCSUCC or TPEV_SVCFAIL, the tpurcode() global contains an application-defined value that was sent as part of tpreturn(). The function tpsend() returns -1 on error and sets tperrno to indicate the error condition. Also, if an event exists and no errors were encountered, tpsend() returns -1 and tperrno is set to [TPEEVENT].

Errors

Upon failure, tpsend() sets tperrno to one of the following values:

[TPEINVAL]

Invalid arguments were given (for example, data does not point to a buffer allocated by tpalloc() or flags are invalid).

[TPEBADDESC]

cd is invalid.

[TPETIME]

This error code indicates that either a timeout has occurred or tpsend() has been attempted, in spite of the fact that the current transaction is already marked rollback only.

If the caller is in transaction mode, then either the transaction is already rollback only or a transaction timeout has occurred. The transaction is marked abort-only. If the caller is not in transaction mode, a blocking timeout has occurred. (A blocking timeout cannot occur if TPNOBLOCK and/or TPNOTIME is specified.)

If a transaction timeout has occurred, then, with one exception, any attempts to send new requests or receive outstanding replies will fail with TPETIME until the transaction has been aborted. The exception is a request that does not block, expects no reply, and is not sent on behalf of the caller's transaction (that is, tpacall() with TPNOTRAN, TPNOBLOCK, and TPNOREPLY set).

When a transactional ATMI call fails inside a transaction, the transaction is put into the <code>TX_ROLLBACK_ONLY</code> state. This state is treated, for most purposes, as though it were equivalent to a timeout. All further ATMI calls for this transaction (with the exception of those issued in the circumstances described in the previous paragraph) will fail with <code>TPETIME</code>.

[TPEEVENT]

An event occurred. data is not sent when this error occurs. The event type is returned in revent.

[TPEBLOCK]

A blocking condition exists and TPNOBLOCK was specified.

[TPGOTSIG]

A signal was received and TPSIGRSTRT was not specified.

[TPEPROTO]

tpsend() was called in an improper context (for example, the connection was established such that the calling program can only receive data).

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

Introduction to the C Language Application-to-Transaction Monitor Interface

[TPEOS]

An operating system error has occurred.

See Also tpalloc(3c), tpconnect(3c), tpdiscon(3c), tprecv(3c), tpservice(3c)

tpservice(3c)

Name tpservice()—Template for service routines.

Description

tpservice() is the template for writing service routines. This template is used for services that receive requests via tpcall(), tpacall() or tpforward() routines as well as by services that communicate via tpconnect(), tpsend() and tprecv() routines.

Service routines processing requests made via either tpcall() or tpacall() receive at most one incoming message (in the data element of svcinfo) and send at most one reply (upon exiting the service routine with tpreturn()).

Conversational services, on the other hand, are invoked by connection requests with at most one incoming message along with a means of referring to the open connection. When a conversational service routine is invoked, either the connecting program or the conversational service may send and receive data as defined by the application. The connection is half-duplex in nature meaning that one side controls the conversation (that is, it sends data) until it explicitly gives up control to the other side of the connection.

Concerning transactions, service routines can participate in at most one transaction if invoked in transaction mode. As far as the service routine writer is concerned, the transaction ends upon returning from the service routine. If the service routine is not invoked in transaction mode, then the service routine may originate as many transactions as it wants using tpbegin(), tpcommit(), and tpabort(). Note that tpreturn() is not used to complete a transaction. Thus, it is an error to call tpreturn() with an outstanding transaction that originated within the service routine.

Service routines are invoked with one argument: svcinfo, a pointer to a service information structure. This structure includes the following members:

```
char
char
char
char
long
long
long
int
cd;
long
appkey;
CLIENTID
cltid;
```

name is populated with the service name that the requester used to invoke the service.

The setting of *flags* upon entrance to a service routine indicates attributes which the service routine may want to note. The following are the possible values for *flags*:

TPCONV

A connection request for a conversation has been accepted and the descriptor for the conversation is available in cd. If not set, then this is a request/response service and cd is not valid.

TPTRAN

The service routine is in transaction mode.

TPNOREPLY

The caller is not expecting a reply. This option will not be set if TPCONV is set.

TPSENDONLY

The service is invoked such that it can only send data across the connection and the program on the other end of the connection can only receive data. This flag is mutually exclusive with TPRECVONLY and may be set only when TPRONY is also set

TPRECVONLY

The service is invoked such that it can only receive data from the connection and the program on the other end of the connection can only send data. This flag is mutually exclusive with TPSENDONLY and may be set only when TPCONV is also set

data points to the data portion of a request message and <code>len</code> is the length of the data. The buffer pointed to by <code>data</code> was allocated by <code>tpalloc()</code> in the communication manager. This buffer may be grown by the user with <code>tprealloc()</code>; however, it cannot be freed by the user. It is recommended that this buffer be the one passed to either <code>tpreturn()</code> or <code>tpforward()</code> when the service ends. If a different buffer is passed to those routines, then that buffer is freed by them. Note that the buffer pointed to by <code>data</code> will be overwritten by the next service request even if this buffer is not passed to <code>tpreturn()</code> or <code>tpforward()</code>. <code>data</code> may be NULL if no data accompanied the request. In this case, <code>len</code> will be 0.

When TPCONV is set in flags, cd is the connection descriptor that can be used with tpsend() and tprecv() to communicate with the program that initiated the conversation.

appkey is set to the application key assigned to the requesting client by the application defined authentication service. This key value is passed along with any and all service requests made while within this invocation of the service routine. appkey will have a value of -1 for originating clients that do not pass through the application authentication service.

cltid is the unique client identifier for the originating client associated with this service request. The definition of this structure is made available to the application in atmi.h solely so that client identifiers may be passed between application servers if necessary. Therefore, the semantics of the fields defined below are not documented and applications should not manipulate the contents of CLIENTID structures. Doing so will invalidate the structures. The CLIENTID structure includes the following member:

```
long clientdata[4];
```

Note that for C++, the service function must have C linkage. This is done by declaring the function as 'extern "C."

Return Values

A service routine does not return any value to its caller, the communication manager dispatcher; thus, it is declared as a void. Service routines, however, are expected to terminate using either tpreturn() or tpforward(). A conversational service routine must use tpreturn(), and cannot use tpforward(). If a service routine returns without using either tpreturn() or tpforward() (that is, it uses the C language return statement or just simply "falls out of the function") or tpforward() is called from a conversational server, the server will print a warning message in a log file and return a service error to the originator or requester. All open connections to subordinates will be disconnected immediately, and any outstanding asynchronous replies will be marked stale. If the server was in transaction mode at the time of failure, the transaction is marked abort-only. Note also that if either tpreturn() or tpforward() are used outside of a service routine (for example, in clients, or in tpsvrinit() or tpsvrdone()), then these routines simply return having no effect.

Frrors

Since tpreturn() ends the service routine, any errors encountered either in handling arguments or in processing cannot be indicated to the function's caller. Such errors cause tperrno to be set to TPESVCERR for a program receiving the service's outcome via either tpcall() or tpgetrply(), and cause the event, TPEV_SVCERR, to be sent over the conversation to a program using tpsend() or tprecv().

See Also tpalloc(3c), tpbegin(3c), tpcall(3c), tpconnect(3c), tpforward(3c), tpreturn(3c), servopts(5)

tpsetctxt(3c)

Name tpsetctxt()—Sets a context identifier for the current application association.

Synopsis #include <atmi.h>
 int tpsetctxt(TPCONTEXT T context, long flags)

Description tpsetctxt() defines the context in which the current thread operates. This function operates on a per-thread basis in a multithreaded environment, and on a per-process basis in a non-threaded environment

Subsequent BEA Tuxedo ATMI calls made in this thread reference the application indicated by context. The context should have been provided by a previous call to tpgetctxt() in one of the threads of the same process. If the value of context is TPNULLCONTEXT, then the current thread is disassociated from any BEA Tuxedo ATMI context.

You can put an individual thread in a process operating in multicontext mode into the TPNULLCONTEXT state by issuing the following call:

tpsetctxt(TPNULLCONTEXT, 0)

TPINVALIDCONTEXT is not a valid input value for context.

A thread in the TPINVALIDCONTEXT state is prohibited from issuing calls to most ATMI functions. (For a complete list of the functions that may and may not be called, see "Introduction to the C Language Application-to-Transaction Monitor Interface.".) Therefore, you may sometimes need to move a thread out of the TPINVALIDCONTEXT state. To do so, call tpsetctxt() with context set to TPNULLCONTEXT or another valid context. (It is also allowable to call the tpterm() function to exit from the TPINVALIDCONTEXT state.)

The second argument, *flags*, is not currently used and must be set to 0.

A thread in a multithreaded application may issue a call to tpsetctxt() while running in any context state, including TPINVALIDCONTEXT.

Return Values Upon successful completion, tpsetctxt() returns a non-negative value.

Upon failure, it leaves the calling process in its original context, returns a value of -1, and sets tperrno to indicate the error condition.

Errors Upon failure, tpsetctxt() sets tperrno to one of the following values:

[TPEINVAL]

Invalid arguments have been given. For example, *flags* has been set to a value other than 0 or the context is TPINVALIDCONTEXT.

[TPENOENT]

The value of context is not a valid context.

[TPEPROTO]

tpsetctxt() has been called in an improper context. For example: (a) it has been called in a server-dispatched thread; (b) it has been called in a process that has not called tpinit(); (c) it has been called in a process that has called tpinit() without specifying the TPMULTICONTEXTS flag; or (d) it has been called from more than one thread in a process where the TMNOTHREADS environment variable has been turned on.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error has been written to a log file.

[TPEOS]

An operating system error has occurred.

See Also Introduction to the C Language Application-to-Transaction Monitor Interface, tpgetctxt(3c)

tpsetmbenc(3c)

Name tpsetmbenc()—Sets the code-set encoding name for a typed buffer.

Synopsis

```
#include <atmi.h>
extern int tperrno;
int
tpsetmbenc(char *bufp, char *enc name, long flags)
```

Description

This function is used for setting or resetting the codeset encoding name. The encoding name is sent along with the input typed buffer. A process receiving these message can use tpgetmbenc() to retrieve this encoding name.

tpsetmbenc() sets the codeset encoding name to be included with a Tuxedo system request. Once this function sets a non-NULL encoding name in the caller's buffer, all requests sent (via tpcall(), tpsend()) include this string until reset or unset. An initial codeset encoding name is applied to a MBSTRING buffer, during tpalloc(), using the TPMBENC environment variable. An MBSTRING buffer without an encoding name defined is invalid.

The bufp argument is a valid pointer to a typed buffer with an encoding name.

The enc_name argument is the encoding name to use to identify the codeset encoding.

The flags argument is 0 or RM_ENC. For RM_ENC the encoding name will be removed from the MBSTRING buffer and the enc_name argument will be ignored. Note that an MBSTRING buffer without an encoding name will fail the _tmconvmb() conversion.

Return Values

Upon success, tpsetmbenc() returns a 0 value otherwise it returns a non-zero on error and sets tperrno to indicate the error condition. This function may fail for the following reasons.

```
[TPEINVAL]
```

buf, enc_name argument is NULL or enc_name is not a valid name to use.

[TPESYSTEM]

A Tuxedo system error has occurred. (e.g. bufp does not correspond to a valid Tuxedo buffer, could not add or remove the encoding name from the buffer)

See Also

```
\label{eq:tpalloc(3c),tpconvmb(3c),tpgetmbenc(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpservice(3c),tpserv
```

tpsetunsol(3c)

Name tpsetunsol()—Sets the method for handling unsolicited messages.

Synopsis #include <atmi.h>

void (*tpsetunsol (void (_TMDLLENTRY *)(*disp) (char *data, long
len, long flags))) (char *data, long len, long flags)

Description

tpsetunsol() allows a client to identify the routine that should be invoked when an unsolicited message is received by the BEA Tuxedo ATMI system libraries. Before the first call to tpsetunsol(), any unsolicited messages received by the BEA Tuxedo ATMI system libraries on behalf of the client are logged and ignored. A call to tpsetunsol() with a NULL function pointer has the same effect. The method used by the system for notification and detection is determined by the application default, which can be overridden on a per-client basis (see tpinit(3c)).

The function pointer passed on the call to tpsetunsol() must conform to the parameter definition given. data points to the typed buffer received and len is the length of the data. flags are currently unused. data can be NULL if no data accompanied the notification. data may be of a buffer type/subtype that is not known by the client, in which case the message data is unintelligible.

data cannot be freed by application code. However, the system frees it and invalidates the data area following return.

Processing within the application's unsolicited message handling routine is restricted to the following BEA Tuxedo ATMI functions: tpalloc(), tpfree(), tpgetctxt(), tpgetlev(), tprealloc(), and tptypes().

Note that in a multithreaded programming environment, it is possible for an unsolicited message handling routine to call tpgetctxt(), create another thread, have that thread call tpsetctxt() to the appropriate context, and have the new thread use the full set of ATMI functions that are available to clients.

If tpsetunsol() is called from a thread that is not currently associated with a context, this establishes a per-process default unsolicited message handler for all new tpinit() contexts created. It has no effect on contexts already associated with the system. A specific context may change this default unsolicited message handler by calling tpsetunsol() again when the context is active. The per-process default unsolicited message handler may be changed by again calling tpsetunsol() in a thread not currently associated with a context.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpsetunsol().

Introduction to the C Language Application-to-Transaction Monitor Interface

Return Values

Upon success, tpsetunsol() returns the previous setting for the unsolicited message handling routine. (NULL is a successful return indicating that no message handling function had been set previously.)

Upon failure, it returns TPUNSOLERR and sets tperrno to indicate the error condition.

Errors Upo

Upon failure, tpsetunsol() sets tperrno to one of the following values:

[TPEPROTO]

tpsetunsol() has been called in an improper context. For example, it has been called from within a server.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

Portability

The interfaces described in <code>tpnotify(3c)</code> are supported on native site UNIX-based and Windows processors. In addition, the routines <code>tpbroadcast()</code> and <code>tpchkunsol()</code>, as well as the function <code>tpsetunsol()</code>, are supported on UNIX and MS-DOS workstation processors.

See Also tpinit(3c), tpterm(3c)

tpsign(3c)

Name tpsign()—Marks a typed message buffer for digital signature.

Synopsis #include <atmi.h>

int tpsign(char *data, TPKEY hKey, long flags)

Description tpsign() marks, or registers, a message buffer for digital signature on behalf of the

principal associated with hKey.

data must point to a valid typed message buffer either (1) previously allocated by a process calling tpalloc() or (2) delivered by the system to a receiving process. The content of the buffer may be modified after tpsign() is invoked.

When the buffer pointed to by data is transmitted from a process, the public key software generates and attaches a digital signature to the message buffer for each digital-signature registration request. A digital signature enables a receiving process to verify the signer (originator) of the message.

The *flags* argument is reserved for future use and must be set to 0.

Return Values On failure, this function returns -1 and sets tperrno to indicate the error condition.

Errors [TPEINVAL]

Invalid arguments were given. For example, hKey is not a valid key for signing or the value of data is NULL.

[TPESYSTEM]

An error occurred. Consult the system error log file for details.

See Also tpkey_close(3c), tpkey_open(3c)

tpsprio(3c)

Name tpsprio()—Sets the service request priority.

Synopsis #include <atmi.h>
 int tpsprio(prio, flags)

Description

tpsprio() sets the priority for the next request sent or forwarded by the current thread in the current context. The priority set affects only the next request sent. Priority can also be set for messages enqueued or dequeued by tpenqueue() or tpdequeue(), if the queued message facility is installed. By default, the setting of prio increments or decrements a service's default priority up to a maximum of 100 or down to a minimum of 1, depending on its sign, where 100 is the highest priority. The default priority for a request is determined by the service to which the request is being sent. This default may be specified administratively (see UBBCONFIG(5)), or take the system default of 50. tpsprio() has no effect on messages sent via tpconnect() or tpsend().

A lower priority message does not remain enqueued forever because every tenth message is retrieved on a "first in, first out" (FIFO) basis. Response time should not be a concern of the lower priority interface or service.

In a multithreaded application tpsprio() operates on a per-thread basis.

The following is a list of valid flags:

TPABSOLUTE

The priority of the next request should be sent out at the absolute value of prio. The absolute value of prio must be within the range 1 and 100, inclusive, with 100 being the highest priority. Any value outside of this range causes a default value to be used.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpsprio().

Return Values

Upon failure, tpsprio() returns -1 and sets tperrno to indicate the error condition.

Errors

Upon failure, tpsprio () sets tperrno to one of the following values:

[TPEINVAL]

flags are invalid.

[TPEPROTO]

tpsprio() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

See Also tpacall(3c), tpcall(3c), tpdequeue(3c), tpenqueue(3c), tpgprio(3c)

tpstrerror(3c)

Name tpstrerror()—Gets error message string for a BEA Tuxedo ATMI system error.

Description

tpstrerror() is used to retrieve the text of an error message from LIBTUX_CAT. err is the error code set in tperrno when a BEA Tuxedo ATMI system function call returns a -1 or other failure value.

You can use the pointer returned by tpstrerror() as an argument to userlog() or the UNIX function fprintf().

A thread in a multithreaded application may issue a call to tpstrerror() while running in any context state, including TPINVALIDCONTEXT.

Return Values

Upon success, tpstrerror() returns a pointer to a string that contains the error message text.

If err is an invalid error code, tpstrerror () returns a NULL.

Errors Upon failure, tpstrerror() returns a NULL but does not set tperrno.

Example

See Also

userlog(3c), Fstrerror, Fstrerror32(3fml)

tpstrerrordetail(3c)

Name tpstrerrordetail()—Gets error detail message string for a BEA Tuxedo ATMI system error.

Synopsis #include <atmi.h>

char * tpstrerrordetail(int err, long flags)

Description tpstrerrordetail() is used to retrieve the text of an error detail of a BEA Tuxedo ATMI system error. err is the value returned by tperrordetail().

The user can use the pointer returned by tpstrerrordetail() as an argument to userlog() or the UNIX function fprintf().

Currently *flags* is reserved for future use and must be set to 0.

A thread in a multithreaded application may issue a call to tpstrerrordetail() while running in any context state, including TPINVALIDCONTEXT.

Return Values Upon success, the function returns a pointer to a string that contains the error detail message text.

Upon failure (that is, if err is an invalid error code), tpstrerrordetail () returns a NULL.

Errors Upon failure, tpstrerrordetail() returns a NULL but does not set tperrno.

See Also Introduction to the C Language Application-to-Transaction Monitor Interface, tperrordetail(3c), tpstrerror(3c), userlog(3c), tperrno(5)

tpsubscribe(3c)

Name tpsubscribe()—Subscribes to an event.

Synopsis #include <atmi.h>

long tpsubscribe(char *eventexpr, char *filter, TPEVCTL *ctl, long
flags)

Description

The caller uses tpsubscribe () to subscribe to an event or set of events named by eventexpr. Subscriptions are maintained by the BEA Tuxedo ATMI EventBroker, TMUSREVT (5), and are used to notify subscribers when events are posted via tppost (). Each subscription specifies a notification method which can take one of three forms: client notification, service calls, or message enqueuing to stable-storage queues. Notification methods are determined by the subscriber's process type and the arguments passed to tpsubscribe().

The event or set of events being subscribed to is named by <code>eventexpr</code>, a NULL-terminated string of at most 255 characters containing a regular expression. For example, if <code>eventexpr</code> is "\e\e..*", the caller is subscribing to all system-generated events; if <code>eventexpr</code> is "\e\e.SysServer.*", the caller is subscribing to all system-generated events related to servers. If <code>eventexpr</code> is "[A-Z].*", the caller is subscribing to all user events starting with A-Z; if <code>eventexpr</code> is ".* (ERR|err).*", the caller is subscribing to all user events containing either the substring ERR or the substring err in the event name. Events called <code>account_error</code> and <code>ERROR_STATE</code>, for example, would both qualify. For more information on regular expressions, see "Regular Expressions" on page 248.

If present, filter is a string containing a Boolean filter rule that must be evaluated successfully before the EventBroker posts the event. Upon receiving an event to be posted, the EventBroker applies the filter rule, if one exists, to the posted event's data. If the data passes the filter rule, the EventBroker invokes the notification method; otherwise, the broker does not invoke the associated notification method. The caller can subscribe to the same event multiple times with different filter rules.

Filter rules are specific to the typed buffers to which they are applied. For FML and view buffers, the filter rule is a string that can be passed to each's Boolean expression compiler (see Fboolco(3fml) and Fvboolco(3fml), respectively) and evaluated against the posted buffer (see Fboolev(3fml) and Fvboolev(3fml), respectively). For STRING buffers, the filter rule is a regular expression. All other buffer types require customized filter evaluators (see buffer(3c) and typesw(5) for details on adding customized filter evaluators). filter is a NULL-terminated string of at most 255 characters.

If the subscriber is a BEA Tuxedo ATMI system client process and ctl is NULL, then the EventBroker sends an unsolicited message to the subscriber when the event to which it subscribed is posted. That is, when an event name is posted that evaluates successfully against eventexpr, the EventBroker tests the posted data against the filter rule associated with eventexpr. If the data passes the filter rule or if there is no filter rule for the event, then the subscriber receives an unsolicited notification along with any data posted with the event. In order to receive unsolicited notifications, the client must register (via tpsetunsol()) an unsolicited message handling routine. If a BEA Tuxedo ATMI system server process calls tpsubscribe() with a NULL ctl parameter, then tpsubscribe() fails setting tperrno to TPEPROTO.

Clients receiving event notification via unsolicited messages should remove their subscriptions from the EventBroker's list of active subscriptions before exiting (see tpunsubscribe(3c) for details). Using tpunsubscribe()'s wildcard handle, -1, clients can conveniently remove all of their "non-persistent" subscriptions which include those associated with the unsolicited notification method (see the description of TPEVPERSIST below for subscriptions and their associated notification methods that persist after a process exits). If a client exits without removing its non-persistent subscriptions, then the EventBroker will remove them when it detects that the client is no longer accessible.

If the subscriber (regardless of process type) wants event notifications to go to service routines or to stable-storage queues, then the ctl parameter must point to a valid TPEVCTL structure. This structure contains the following elements:

```
long flags;
char name1[32];
char name2[32];
TPQCTL qctl;
```

The following is a list of valid bits for the $ct1 \rightarrow flags$ element controlling options for event subscriptions:

TPEVSERVICE

Setting this flag indicates that the subscriber wants event notifications to be sent to the BEA Tuxedo ATMI system service routine named in ct1->name1. That is, when an event name is posted that evaluates successfully against eventexpr, the EventBroker tests the posted data against the filter rule associated with eventexpr. If the data passes the filter rule or if there is no filter rule for the event, then a service request is sent to ct1->name1 along with any data posted with the event. The service name in ct1->name1 can be any valid BEA Tuxedo ATMI system service name and it may or may not be active at the time the subscription is made. Service

routines invoked by the EventBroker should return with no reply data. That is, they should call tpreturn() with a NULL data argument. Any data passed to tpreturn() will be dropped. TPEVSERVICE and TPEVQUEUE are mutually exclusive flags.

If TPEVTRAN is also set in $ctl \rightarrow flags$, then if the process calling tppost () is in transaction mode, the EventBroker calls the subscribed service routine such that it will be part of the poster's transaction. Both the EventBroker, TMUSREVT (5), and the subscribed service routine must belong to server groups that support transactions (see UBBCONFIG (5) for details). If TPEVTRAN is not set in $ctl \rightarrow flags$, then the EventBroker calls the subscribed service routine such that it will not be part of the poster's transaction

TPEVOUEUE

Setting this flag indicates that the subscriber wants event notifications to be enqueued to the queue space named in ct1->name1 and the queue named in ct1->name2. That is, when an event name is posted that evaluates successfully against eventexpr, the EventBroker tests the posted data against the filter rule associated with eventexpr. If the data passes the filter rule or if there is no filter rule for the event, then the EventBroker enqueues a message to the queue space named in ct1->name1 and the queue named in ct1->name2 along with any data posted with the event. The queue space and queue name can be any valid BEA Tuxedo ATMI system queue space and queue name, either of which may or may not exist at the time the subscription is made.

ct1->qct1 can contain options further directing the EventBroker's enqueuing of the posted event. If no options are specified, then ct1->qct1.flags should be set to TPNOFLAGS. Otherwise, options can be set as described in the "Control Parameter" subsection of tpenqueue (3c) (specifically, see the section describing the valid list of flags controlling input information for tpenqueue (3c)). TPEVSERVICE and TPEVQUEUE are mutually exclusive flags.

If TPEVTRAN is also set in $ctl \rightarrow flags$, then if the process calling tppost () is in transaction mode, the EventBroker enqueues the posted event and its data such that it will be part of the poster's transaction. The EventBroker, TMUSREVT (5), must belong to a server group that supports transactions (see UBBCONFIG (5) for details). If TPEVTRAN is not set in $ctl \rightarrow flags$, then the EventBroker enqueues the posted event and its data such that it will not be part of the poster's transaction.

TPEVTRAN

Setting this flag indicates that the subscriber wants the event notification for this subscription to be included in the poster's transaction, if one exists. If the poster is not a transaction, then a transaction is started for this event notification. If this flag is not set, then any events posted for this subscription will not be done on behalf of any transaction in which the poster is participating. This flag can be used with either TPEVSERVICE OF TPEVQUEUE.

TPEVPERSIST

By default, the BEA Tuxedo EventBroker deletes subscriptions when the resource to which it is posting is not available (for example, the EventBroker cannot access a service routine and/or a queue space/queue name associated with an event subscription). Setting this flag indicates that the subscriber wants this subscription to persist across such errors (usually because the resource will become available again in the future). When this flag is not used, the EventBroker will remove this subscription if it encounters an error accessing either the service name or queue space/queue name designated in this subscription.

If this flag is used with TPEVTRAN and the resource is not available at the time of event notification, then the EventBroker will return to the poster such that its transaction must be aborted. That is, even though the subscription remains intact, the resource's unavailability will cause the poster's transaction to fail.

If the EventBroker's list of active subscriptions already contains a subscription that matches the one being requested by tpsubscribe(), then the function fails setting tperrno to TPEMATCH. For a subscription to match an existing one, both eventexpr and filter must match those of a subscription already in the EventBroker's active list of subscriptions. In addition, depending on the notification method, other criteria are used to determine matches.

If the subscriber is a BEA Tuxedo ATMI system client process and ctl is NULL (such that the caller receives unsolicited notifications when events are posted), then its system-defined client identifier (known as a CLIENTID) is also used to detect matches. That is, tpsubscribe() fails if eventexpr, filter, and the caller's CLIENTID match those of a subscription already known to the EventBroker.

If the caller has set <code>ctl->flags</code> to <code>TPEVSERVICE</code>, then <code>tpsubscribe()</code> fails if <code>eventexpr</code>, <code>filter</code>, and the service name set in <code>ctl->name1</code> match those of a subscription already known to the EventBroker.

For subscriptions to stable-storage queues, the queue space, queue name, and correlation identifier are used, in addition to <code>eventexpr</code> and <code>filter</code>, when determining matches. The correlation identifier can be used to differentiate among several subscriptions for the same event expression and filter rule, destined for the same queue. Thus, if the caller has set <code>ctl->flags</code> to <code>TPEVQUEUE</code>, and <code>TPQCOORID</code> is not set in <code>ctl->qctl.flags</code>, then <code>tpsubscribe()</code> fails if <code>eventexpr</code>, <code>filter</code>, the queue space name set in <code>ctl->name1</code>, and the queue name set in <code>ctl->name2</code> match those of a subscription (which also does not have a correlation identifier specified) already known to the EventBroker. Further, if <code>TPQCOORID</code> is set in <code>ctl->qctl.flags</code>, then <code>tpsubscribe()</code> fails if <code>eventexpr</code>, <code>filter</code>, <code>ctl->name1</code>, <code>ctl->name2</code>, and <code>ctl->qctl.corrid</code> match those of a subscription (which has the same correlation identifier specified) already known to the EventBroker.

The following is a list of valid flags for tpsubscribe():

TPNOBLOCK

The subscription is not made if a blocking condition exists. If such a condition occurs, the call fails and tperrno is set to TPEBLOCK. When TPNOBLOCK is not specified and a blocking condition exists, the caller blocks until the condition subsides or a timeout occurs (either transaction or blocking timeout).

TPNOTIME

This flag signifies that the caller is willing to block indefinitely and wants to be immune to blocking timeouts. Transaction timeouts may still occur.

TPSIGRSTRT

If a signal interrupts any underlying system calls, then the interrupted system call is reissued. When TPSIGRSTRT is not specified and a signal interrupts a system call, then tpsubscribe() fails and tperrno is set to TPGOTSIG.

In a multithreaded application, a thread in the ${\tt TPINVALIDCONTEXT}$ state is not allowed to issue a call to ${\tt tpsubscribe}$ ().

Regular Expressions

The regular expressions described in Table 12 are much like those used in the UNIX system editor, ed(1). The alternation operator, (|), has been added along with some other practical things. In general, however, there should be few surprises.

Regular expressions (REs) are constructed by applying any of the following production rules one or more times.

Table 12 Regular Expressions

Rule	Matching Text
character	Itself (character is any ASCII character except the special ones mentioned below).
\ character	Itself except as follows: \\—newline \\t—tab \\b—backspace \\r—carriage return \\f—formfeed
\ special-character	Its unspecial self. The special characters are . * + ? () [{ and \\—Any character except the end-of-line character (usually newline or NULL). ^—Beginning of the line. \$—End-of-line character.
[class]	any character in the class denoted by a sequence of characters and/or ranges. A range is given by the construct <i>character-character</i> . For example, the character class, [a-zA-Z0-9_], will match any alphameric character or "_". To be included in the class, a hyphen, "-", must be escaped (preceded by a "\\") or appear first or last in the class. A literal "]" must be escaped or appear first in the class. A literal "^" must be escaped if it appears first in the class.
[^ class]	Any character in the complement of the class with respect to the ASCII character set, excluding the end-of-line character.
RE RE	The sequence. (catenation)
RE RE	Either the left RE or the right RE. (left to right alternation)
RE *	Zero or more occurrences of RE.
RE +	One or more occurrences of RE.
RE ?	Zero or one occurrences of RE.
RE { n }	n occurrences of RE. n must be between 0 and 255, inclusive.
RE { m, n }	m through n occurrences of RE, inclusive. A missing m is taken to be zero. A missing n denotes m or more occurrences of RE.

Table 12 Regular Expressions (Continued	Table	12 Regular	Expressions	(Continued
---	-------	------------	-------------	------------

Rule	Matching Text
(RE)	Explicit precedence/grouping.
(RE) \$ n	The text matching RE is copied into the <i>n</i> th user buffer. <i>n</i> may be 0 through 9. User buffers are cleared before matching begins and loaded only if the entire pattern is matched.

There are three levels of precedence. In order of decreasing binding strength they are:

- catenation closure (*,+,?,{...})
- catenation
- alternation (|)

As indicated above, parentheses are used to give explicit precedence.

Return Values

Upon successful completion, tpsubscribe() returns a handle that can be used to remove this subscription from the EventBroker's list of active subscriptions. The subscriber or any other process is allowed to use the returned handle to delete this subscription.

Upon failure, tpsubscribe() returns -1 and sets tperrno to indicate the error condition.

Frrors

Upon failure, tpsubscribe() sets tperrno to one of the following values. (Unless otherwise noted, failure does not affect the caller's transaction, if one exists.)

[TPEINVAL]

Invalid arguments were given (for example, eventexpr is NULL).

[TPENOENT]

Cannot access the BEA Tuxedo EventBroker.

[TPELIMIT]

The subscription failed because the EventBroker's maximum number of subscriptions has been reached.

[TPEMATCH]

The subscription failed because it matched one already listed with the EventBroker.

[TPEPERM]

The client is not attached as tpsysadm and the subscription action is either a service call or the enqueuing of a message.

[TPETIME]

This error code indicates that either a timeout has occurred or tpsubscribe() has been attempted, in spite of the fact that the current transaction is already marked rollback only.

If the caller is in transaction mode, then either the transaction is already rollback only or a transaction timeout has occurred. The transaction is marked abort-only. If the caller is not in transaction mode, a blocking timeout has occurred. (A blocking timeout cannot occur if TPNOBLOCK and/or TPNOTIME is specified.)

If a transaction timeout has occurred, then, with one exception, any attempts to send new requests or receive outstanding replies will fail with TPETIME until the transaction has been aborted. The exception is a request that does not block, expects no reply, and is not sent on behalf of the caller's transaction (that is, tpacall() with TPNOTRAN, TPNOBLOCK, and TPNOREPLY set).

When a transactional ATMI call fails inside a transaction, the transaction is put into the <code>TX_ROLLBACK_ONLY</code> state. This state is treated, for most purposes, as though it were equivalent to a timeout. All further ATMI calls for this transaction (with the exception of those issued in the circumstances described in the previous paragraph) will fail with <code>TPETIME</code>.

[TPEBLOCK]

A blocking condition exists and TPNOBLOCK was specified.

[TPGOTSIG]

A signal was received and TPSIGRSTRT was not specified.

[TPEPROTO]

tpsubscribe() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

See Also

buffer(3c), tpenqueue(3c), tppost(3c), tpsetunsol(3c),
tpunsubscribe(3c), Fboolco, Fboolco32, Fvboolco, Fvboolco32(3fml),
Fboolev, Fboolev32, Fvboolev, Fvboolev32(3fml), EVENTS(5),
EVENT_MIB(5), TMSYSEVT(5), TMUSREVT(5), tuxtypes(5), typesw(5),
UBBCONFIG(5)

tpsuspend(3c)

Name tpsuspend()—Suspends a global transaction.

Synopsis #include <atmi.h>

int tpsuspend(TPTRANID *tranid, long flags)

Description

tpsuspend() is used to suspend the transaction active in the caller's process. A transaction begun with tpbegin() may be suspended with tpsuspend(). Either the suspending process or another process may use tpresume() to resume work on a suspended transaction. When tpsuspend() returns, the caller is no longer in transaction mode. However, while a transaction is suspended, all resources associated with that transaction (such as database locks) remain active. Like an active transaction, a suspended transaction is susceptible to the transaction timeout value that was assigned when the transaction first began.

For the transaction to be resumed in another process, the caller of tpsuspend() must have been the initiator of the transaction by explicitly calling tpbegin(). tpsuspend() may also be called by a process other than the originator of the transaction (for example, a server that receives a request in transaction mode). In the latter case, only the caller of tpsuspend() may call tpresume() to resume that transaction. This case is allowed so that a process can temporarily suspend a transaction to begin and do some work in another transaction before completing the original transaction (for example, to run a transaction to log a failure before rolling back the original transaction).

tpsuspend() returns in the space pointed to by tranid the transaction identifier being suspended. The caller is responsible for allocating the space to which tranid points. It is an error for tranid to be NULL.

To ensure success, the caller must have completed all outstanding transactional communication with servers before issuing tpsuspend(). That is, the caller must have received all replies for requests sent with tpacall() that were associated with the caller's transaction. Also, the caller must have closed all connections with conversational services associated with the caller's transaction (that is, tprecv() must have returned the TPEV_SVCSUCC event). If either rule is not followed, then tpsuspend() fails, the caller's current transaction is not suspended and all transactional communication descriptors remain valid. Communication descriptors not associated with the caller's transaction remain valid regardless of the outcome of tpsuspend().

Currently, *flags* are reserved for future use and must be set to 0.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpsuspend().

Return Value

tpsuspend() returns -1 on error and sets tperrno to indicate the error condition.

Errors

Under the following conditions, tpsuspend() fails and sets tperrno to:

[TPEINVAL]

tranid is a NULL pointer or flags is not 0. The caller's state with respect to the transaction is not changed.

[TPEABORT]

The caller's active transaction has been aborted. All communication descriptors associated with the transaction are no longer valid.

[TPEPROTO]

tpsuspend() was called in an improper context (for example, the caller is not in transaction mode). The caller's state with respect to the transaction is not changed.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

See Also

tpacall(3c), tpbegin(3c), tprecv(3c), tpresume(3c)

tpsvrdone(3c)

Name tpsvrdone()—Terminates a BEA Tuxedo ATMI system server.

Description

The BEA Tuxedo ATMI system server abstraction calls <code>tpsvrdone()</code> after it has finished processing service requests but before it exits. When this routine is invoked, the server is still part of the system but its own services have been unadvertised. Thus, BEA Tuxedo ATMI system communication can be performed and transactions can be defined in this routine. However, if <code>tpsvrdone()</code> returns with open connections, asynchronous replies pending or while still in transaction mode, the BEA Tuxedo ATMI system will close its connections, ignore any pending replies, and abort the transaction before the server exits.

If a server is shut down by the invocation of tmshutdown -y, services are suspended and the ability to perform communication or to begin transactions in tpsvrdone() is limited.

If an application does not provide this routine in a server, then the default version provided by the BEA Tuxedo ATMI system is called instead. If a server has been defined as a single-threaded server, the default tpsvrdone() calls tpsvrthrdone(), and the default version of tpsvrthrdone() calls tx_close(). If a server has been defined as a multithreaded server, tpsvrthrdone() is called in each server dispatch thread, but is not called from tpsvrdone(). Regardless of whether the server is multithreaded, the default tpsvrdone() calls userlog to indicate that the server is about to exit.

Usage When called in tpsvrdone(), the tpreturn() and tpforward() functions simply return with no effect.

See Also tpsvrthrdone (3c), tpsvrthrinit (3c), servopts (5)

tpsvrinit(3c)

Name tpsyrinit()—Initializes a BEA Tuxedo system server.

Synopsis #include <atmi.h>

int tpsvrinit(int argc, char **argv)

Description

The BEA Tuxedo ATMI system server abstraction calls tpsvrinit() during its initialization. This routine is called after the thread of control has become a server but before it handles any service requests; thus, BEA Tuxedo ATMI system communication may be performed and transactions may be defined in this routine. However, if tpsvrinit() returns with either open connections or asynchronous replies pending, or while still in transaction mode, the BEA Tuxedo ATMI system closes the connections, ignores any pending replies, and aborts the transaction before the server exits.

If an application does not provide this routine in a server, then the default version provided by the BEA Tuxedo ATMI system is called, instead.

If a server has been defined as a single-threaded server, the default tpsvrinit() calls tpsvrthrinit(), and the default version of tpsvrthrinit() calls $tx_open()$. If a server has been defined as a multithreaded server, tpsvrthrinit() is called in each server dispatch thread, but is not called from tpsvrinit(). Regardless of whether the server is single-threaded or multithreaded, the default version of tpsvrinit() calls userlog() to indicate that the server started successfully.

Application-specific options can be passed into a server and processed in tpsvrinit() (see servopts(5)). The options are passed through argc and argv. Since getopt() is used in a BEA Tuxedo ATMI system server abstraction, optarg(), optind(), and opterr() may be used to control option parsing and error detection in tpsvrinit().

If an error occurs in tpsvrinit(), the application can cause the server to exit gracefully (and not take any service requests) by returning -1. The application itself should not call exit().

When tpsvrinit() returns -1, the system does not restart the server. Instead, the administrator must run tmboot to restart the server.

Return Values A negative return value causes the server to exit gracefully.

When used outside a service routine (for example, in clients, in tpsvrinit(), or in tpsvrdone()), the tpreturn() and tpforward() functions simply return with no effect

Usage

Introduction to the C Language Application-to-Transaction Monitor Interface

See Also tpopen(3c), tpsvrdone(3c), tpsvrthrinit(3c), servopts(5) getopt(3) in a C language reference manual

tpsvrthrdone(3c)

Name tpsyrthrdone ()—Terminates a BEA Tuxedo ATMI server thread.

Synopsis #include <atmi.h>

void tpsvrthrdone (void)

Description

The BEA Tuxedo ATMI server abstraction calls <code>tpsvrthrdone()</code> during the termination of each thread that has been started to handle dispatched service requests. In other words, even if a thread is terminated before it has handled a request, the <code>tpsvrdone()</code> function is called. When this routine is called, the thread of control is still part of the BEA Tuxedo ATMI server, but the thread has finished processing all service requests. Thus, BEA Tuxedo ATMI communication may be performed and transactions may be defined in this routine. However, <code>iftpsvrthrdone()</code> returns with either open connections or asynchronous replies pending, or while still in transaction mode, the BEA Tuxedo ATMI system closes the connections, ignores any pending replies, and aborts the transaction before the server dispatch thread exits.

If an application does not provide this routine in a server, then the default version of tpsvrthrdone() provided by the BEA Tuxedo ATMI system is called instead. The default version of tpsvrthrdone() calls tx close().

tpsvrthrdone() is called even in single-threaded servers. In a single-threaded server, tpsvrthrdone() is called from the default version of tpsvrdone(). In a server with the potential for multiple dispatch threads, tpsvrdone() does not call tpsvrthrdone().

Usage When called from tpsvrthrdone(), the tpreturn() and tpforward() functions simply return with no effect.

tpsvrthrinit(3c)

Name tpsyrthrinit()—Initializes a BEA Tuxedo ATMI server thread.

Synopsis #include <atmi.h>

int tpsvrthrinit(int argc, char **argv)

Description

The BEA Tuxedo ATMI server abstraction calls <code>tpsvrthrinit()</code> during the initialization of each thread that handles dispatched service requests. This routine is called after the thread of control has become part of the BEA Tuxedo ATMI server but before the thread handles any service requests. Thus, BEA Tuxedo ATMI communication may be performed and transactions may be defined in this routine. However, if <code>tpsvrthrinit()</code> returns with either open connections or asynchronous replies pending, or while still in transaction mode, the BEA Tuxedo ATMI system closes the connections, ignores any pending replies, and aborts the transaction before the server dispatch thread exits.

If an application does not provide this routine in a server, then the default version of tpsvrthrinit() provided by the BEA Tuxedo ATMI system is called instead. The default version of tpsvrthrinit() calls tx open().

tpsvrthrinit() is called even in single-threaded servers. In a single-threaded server, tpsvrthrinit() is called from the default version of tpsvrinit(). In a server with the potential for multiple dispatch threads, tpsvrinit() does not call tpsvrthrinit().

Application-specific options can be passed into a server and processed in tpsvrthrinit(). For more information about options, see servopts(5). The options are passed argc and argv. Because getopt() is used in a BEA Tuxedo ATMI server abstraction, optarg(), optind(), and opterr() may be used to control option parsing and error detection in tpsvrthrinit().

If an error occurs in tpsvrthrinit(), the application can cause the server dispatch thread to exit gracefully (and not take any service requests) by returning -1. The application should not call exit() or any operating system thread exit function.

Return Values

A negative return value will cause the server dispatch thread to exit gracefully.

Usage

When used outside a service routine (for example, when used in a client or in tpsvrinit(), tpsvrdone(), tpsvrthrinit(), or tpsvrthrdone()), the tpreturn() and tpforward() functions simply return with no effect.

See Also

tpforward(3c), tpreturn(3c), tpsvrthrdone(3c), tpsvrthrinit(3c),
tx_open(3c), servopts(5)

getopt(3) in a C language reference manual

tpterm(3c)

Name tpterm()—Leaves an application.

Synopsis #include <atmi.h>
 int tpterm(void)

Description

tpterm() removes a client from a BEA Tuxedo ATMI system application. If the client is in transaction mode, then the transaction is rolled back. When tpterm() returns successfully, the caller can no longer perform BEA Tuxedo ATMI client operations. Any outstanding conversations are immediately disconnected.

If tpterm() is called more than once (that is, if it is called after the caller has already left the application), no action is taken and success is returned.

Multithreading and Multicontexting Issues

In good programming practice, all threads but one should either exit or switch context before the single remaining thread issues a call to tpterm(). If this is not done, then the remaining threads are put in a TPINVALIDCONTEXT context. A description of the semantics of this context follows.

When invoked by one thread in a context with which multiple threads are associated, tpterm():

- Operates on all threads in a context, but not on all contexts in a process
- Executes immediately, even if other threads in the same process are still associated with that context

Any thread blocked in an ATMI call when another thread terminates its context will return from the ATMI call with a failure return; tperrno is set to TPESYSTEM. In addition, if tperrordetail() is invoked after such a failure return, it returns TPED INVALIDCONTEXT.

In a single-context application, whenever a single thread calls tpterm(), the context state for all threads is set to TPNULLCONTEXT.

In a multicontexted application, however, when tpterm() is invoked by one thread, all other threads in the same context are placed in a state such that if they subsequently call most ATMI functions, those functions will, instead, return failure with tperrno set to TPEPROTO. Lists of the functions that are allowed and disallowed in such an invalid context state are provided in "Introduction to the C Language

Application-to-Transaction Monitor Interface" on page 7. If a thread in the invalid context state (TPINVALIDCONTEXT) calls the tpgetctxt() function, tpgetctxt() sets the context parameter to TPINVALIDCONTEXT.

A thread may exit from the TPINVALIDCONTEXT state by calling one of the following:

- tpsetctxt() with the TPNULLCONTEXT context or another valid context
- tpterm()

It is forbidden to call tpsetctxt() with a context of TPINVALIDCONTEXT; doing so results in failure with tperrno set to TPEPROTO. When a thread invokes ATMI functions other than tpsetunsol() that do not require the caller to be associated with an application, these functions behave as if they were invoked in the NULL context. Client applications using unsolicited thread notification should explicitly call tpterm() to terminate the unsolicited notification thread.

After invoking tpterm(), a thread is placed in the TPNULLCONTEXT context. Most ATMI functions invoked by a thread in the TPNULLCONTEXT context perform an implicit tpinit(). Whether or not the call to tpinit() succeeds depends on the usual determining factors, unrelated to context-specific or thread-specific issues.

A thread in a multithreaded application may issue a call to tpterm() while running in any context state, including TPINVALIDCONTEXT.

Return Values

Upon success in a single-context application, all threads in the application's current context are placed in the TPNULLCONTEXT state.

Upon success in a multicontexted application, the calling thread is placed in the TPNULLCONTEXT state and all other threads in the same context as the calling thread are placed in the TPINVALIDCONTEXT state. The user may change the context state of the latter threads by running tpsetctxt() with the context argument set to TPNULLCONTEXT or another valid context.

Upon failure, tpterm() leaves the calling process in its original context state, returns -1, and sets tperrno to indicate the error condition.

Frrors

Upon failure, tpterm() sets tperrno to one of the following values:

[TPEPROTO]

tpterm() was called in an improper context (for example, the caller is a server).

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

See Also tpinit(3c), tpgetctxt(3c), tpsetctxt(3c), tpsetunsol(3c)

tptypes(3c)

Name tptypes ()—Routine to determine information about a typed buffer.

Synopsis #include <atmi.h>

long tptypes(char *ptr, char *type, char *subtype)

Description

tptypes () takes as its first argument a pointer to a data buffer and returns the type and subtype of that buffer in its second and third arguments, respectively. ptr must point to a buffer gotten from tpalloc(). If type and subtype are non-NULL, then the function populates the character arrays to which they point with the names of the buffer's type and subtype, respectively. If the names are of their maximum length (8 for type, 16 for subtype), the character array is not NULL-terminated. If no subtype exists, then the array pointed to by subtype will contain a NULL string.

Note that only the first eight bytes of type and the first 16 bytes of subtype are populated.

A thread in a multithreaded application may issue a call to tptypes() while running in any context state, including TPINVALIDCONTEXT.

Return Values

Upon success, tptypes() returns the size of the buffer;

Upon failure, it returns -1 and sets tperrno to indicate the error condition.

Frrors

Upon failure, tptypes() sets tperrno to one of the following values:

[TPEINVAL]

Invalid arguments were given (for example, ptr does not point to a buffer gotten from \S tpalloc()).

[TPEPROTO]

tptypes() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

See Also tpalloc(3c), tpfree(3c), tprealloc(3c)

tpunadvertise(3c)

Name tpunadvertise()—Routine for unadvertising a service name.

Synopsis #include <atmi.h>

int tpunadvertise(char *svcname)

Description

tpunadvertise() allows a server to unadvertise a service that it offers. By default, a server's services are advertised when it is booted and they are unadvertised when it is shut down

All servers belonging to a Multiple Server, Single Queue (MSSQ) set must offer the same set of services. These routines enforce this rule by affecting the advertisements of all servers sharing an MSSQ set.

tpunadvertise() removes <code>svcname</code> as an advertised service for the server (or the set of servers sharing the caller's MSSQ set). <code>svcname</code> cannot be NULL or the NULL string (""). Also, <code>svcname</code> should be 15 characters or less. (See the *SERVICES section of <code>UBBCONFIG(5)</code>). Longer names will be accepted and truncated to 15 characters. Care should be taken such that truncated names do not match other service names.

Return Values

Upon failure, tpunadvertise() returns -1 and sets tperrno to indicate the error condition.

Errors

Upon failure, tpunadvertise() sets tperrno to one of the following values:

[TPEINVAL]

svcname is NULL or the NULL string ("").

[TPENOENT]

svcname is not currently advertised by the server.

[TPEPROTO]

tpunadvertise() was called in an improper context (for example, by a client).

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

See Also tpadvertise(3c)

tpunsubscribe(3c)

Name tpunsubscribe()—Unsubscribes to an event.

Synopsis #include <atmi.h>

int tpunsubscribe(long subscription, long flags)

Description

The caller uses <code>tpunsubscribe()</code> to remove an event subscription or a set of event subscriptions from the BEA Tuxedo EventBroker's list of active subscriptions. <code>subscription</code> is an event subscription handle returned by <code>tpsubscribe()</code>. Setting <code>subscription</code> to the wildcard value, -1, directs <code>tpunsubscribe()</code> to unsubscribe to all non-persistent subscriptions previously made by the calling process. Non-persistent subscriptions are those made without the <code>TPEVPERSIST</code> bit setting in the <code>ctl->flags</code> parameter of <code>tpsubscribe()</code>. Persistent subscriptions can be deleted only by using the handle returned by <code>tpsubscribe()</code>.

Note that the -1 handle removes only those subscriptions made by the calling process and not any made by previous instantiations of the caller (for example, a server that dies and restarts cannot use the wildcard to unsubscribe to any subscriptions made by the original server).

The following is a list of valid flags:

TPNOBLOCK

The subscription is not removed if a blocking condition exists. If such a condition occurs, the call fails and tperrno is set to TPEBLOCK. When TPNOBLOCK is not specified and a blocking condition exists, the caller blocks until the condition subsides or a timeout occurs (either transaction or blocking timeout).

TPNOTIME

This flag signifies that the caller is willing to block indefinitely and wants to be immune to blocking timeouts. Transaction timeouts may still occur.

TPSTGRSTRT

If a signal interrupts any underlying system calls, then the interrupted system call is reissued. When TPSIGRSTRT is not specified and a signal interrupts a system call, then tpunsubscribe() fails and tperrno is set to TPGOTSIG.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tpunsubscribe().

Return Values

Upon completion of tpunsubscribe(), tpurcode() contains the number of subscriptions deleted (zero or greater) from the EventBroker's list of active subscriptions. tpurcode() may contain a number greater than 1 only when the wildcard handle, -1, is used. Also, tpurcode() may contain a number greater than 0 even when tpunsubscribe() completes unsuccessfully (that is, when the wildcard handle is used, the EventBroker may have successfully removed some subscriptions before it encountered an error deleting others).

Upon failure, tpunsubscribe() returns -1 and sets tperrno to indicate the error condition.

Errors

Upon failure, tpunsubscribe () sets tperrno to one of the following values. (Unless otherwise noted, failure does not affect the caller's transaction, if one exists.)

[TPEINVAL]

Invalid arguments were given (for example, *subscription* is an invalid subscription handle).

[TPENOENT]

Cannot access the BEA Tuxedo EventBroker.

[TPETIME]

This error code indicates that either a timeout has occurred or tpunsubscribe() has been attempted, in spite of the fact that the current transaction is already marked rollback only.

If the caller is in transaction mode, then either the transaction is already rollback only or a transaction timeout has occurred. The transaction is marked abort-only. If the caller is not in transaction mode, a blocking timeout has occurred. (A blocking timeout cannot occur if TPNOBLOCK and/or TPNOTIME is specified.)

If a transaction timeout has occurred, then, with one exception, any attempts to send new requests or receive outstanding replies will fail with TPETIME until the transaction has been aborted. The exception is a request that does not block, expects no reply, and is not sent on behalf of the caller's transaction (that is, tpacall() with TPNOTRAN, TPNOBLOCK, and TPNOREPLY set).

When a transactional ATMI call fails inside a transaction, the transaction is put into the <code>TX_ROLLBACK_ONLY</code> state. This state is treated, for most purposes, as though it were equivalent to a timeout. All further ATMI calls for this transaction (with the exception of those issued in the circumstances described in the previous paragraph) will fail with <code>TPETIME</code>.

```
[TPEBLOCK]
```

A blocking condition exists and TPNOBLOCK was specified.

[TPGOTSIG]

A signal was received and TPSIGRSTRT was not specified.

[TPEPROTO]

tpunsubscribe() was called improperly.

[TPESYSTEM]

A BEA Tuxedo system error has occurred. The exact nature of the error is written to a log file.

[TPEOS]

An operating system error has occurred.

See Also

tppost(3c), tpsubscribe(3c), EVENTS(5), EVENT_MIB(5), TMSYSEVT(5),
TMUSREVT(5)

TRY(3c)

```
Name
         TRY () —Exception-returning interface.
Synopsis
         #include <texc.h>
         TRY
         try block
         [ CATCH(exception name) handler block] ...
         [CATCH ALL handler block]
         ENDTRY
         TRY
         try block
         FINALLY
         finally block
         ENDTRY
         RAISE (exception name)
         RERAISE
         /* declare exception */
         EXCEPTION exception name;
         /* initialize address (application) exception */
         EXCEPTION INIT (EXCEPTION exception name)
         /* intialize status exception (map status to exception */
         exc set status (EXCEPTION *exception name, long status)
         /* map status exception to status */
         exc get status (EXCEPTION *exception name, long *status)
         /* compare exceptions */
         exc matches (EXCEPTION *e1, EXCEPTION *e2)
         /* print error to stderr */
         void exc report(EXCEPTION *exception)
```

Description

The TRY/CATCH interface provides a mechanism to handle exceptions without the use of status variables (for example, errno or status variables passed back from an RPC operation). These macros are defined in text.h and this header is automatically included in any header files generated by tidl(1).

The TRY try_block is a block of C or C++ declarations and statements in which an exception may be raised (code that is not associated with raising an exception should be placed before or after the try block). Each TRY/ENDTRY pair constitutes a "scope,"

with respect to exceptions (not unlike C scoping), or a region of code over which exceptions are caught. These scopes can be properly nested. When an exception is raised, an error is reported to the application by searching the active scopes for actions written to handle ("absorb") an exception (CATCH or CATCH_ALL clauses) or complete the scopes (FINALLY clauses). If a scope does not handle an exception, the scope is torn down with the exception raised at the next higher level (unwinding the stack of exception scopes). Execution resumes at the point after which the exception is handled; there is no provision for resuming execution at the point of error. If the exception is not handled by any scope, the program is terminated (a message is written to the log via userlog (3c) and abort(3) is called).

Zero or more occurrences of CATCH (exception_name) handler_block may be provided. Each handler_block is a block of C or C++ declarations and statements in which the associated exception (exception_name) is processed (normally, actions are specified for recovery from the failure). If an exception is raised by a statement in try block, then the first CATCH clause that matches the exception is executed.

Within a CATCH or CATCH_ALL handler_block, the current exception can be referenced by the EXCEPTION pointer THIS_CATCH (for example, for logic based on or printing the exception value).

If the exception is not handled by one of the CATCH clauses, then the CATCH_ALL clause is executed. By default, no further action is taken for an exception that is handled by a CATCH or CATCH_ALL clause. If no CATCH_ALL clause exists, then the exception is raised at the try_block at the next higher level, assuming that the try_block is nested within another try_block . If an ANSI C compiler is used, register and automatic variables that are used in the handler blocks should be declared with the volatile attribute (as is true of any blocks that use setjmp/longjmp). Also note that output parameters and return values from the functions that can generate an exception are indeterminate.

Within a CATCH or CATCH_ALL handler_block, the current exception can be propagated to the next higher level (the exception is "reraised") using the RERAISE statement. The RERAISE statement must appear lexically within the scope of a handler_block (that is, not within a function called by the handler_block). Any exception that is caught but not fully handled should be reraised. In many cases, a CATCH_ALL handler should reraise the exception because the handler is not written to handle every exception. The application should also be written such that an exception is raised to the proper scope such that the handler blocks take the appropriate actions and modify the appropriate state (for example, if an exception occurs while opening a file, the handler function for that level should not try to close the unopened file).

An exception can be raised from anywhere by using the RAISE(exception_name) statement. This statement causes the exception to start propagating at the current try_block and will be reraised until it is handled.

The FINALLY clause can be used to specify an epilogue block of code that is executed after the <code>try_block</code>, whether or not an exception is raised. If an exception is raised in the <code>try_block</code>, it is reraised after the <code>finally_block</code> is executed. This clause can be used to avoid replicating epilogue code twice, once in a <code>CATCH_ALL</code> clause, and again after the <code>ENDTRY</code>. It is normally used to execute cleanup activities, restoring invariants (for example, shared data, locks) as the scopes are unwound, whether or not exceptions are raised (that is, on both normal and abnormal exits from the block). Note (in the "Synopsis" section) that a <code>FINALLY</code> clause cannot be used with a <code>CATCH_ORTCH_ALL</code> clause for the same <code>try_block</code>; use nested <code>try_blocks</code>.

The ENDTRY statement must be used to complete the TRY block, since it contains code that must be executed to make sure that exceptions are handled and the context is cleaned up. A try_block, handler_block, or finally_block must not contain a return, non-local jump, or any other means of leaving the block such that the ENDTRY is not reached (for example, goto(), break(), continue(), longjmp()).

This interface is provided to handle exceptions from RPC operations. However, this is a generic interface that can be used for any application. An exception is declared to be of type EXCEPTION. (This is a complex data type; don't try to use it like a long integer.) There are two types of exceptions. They are declared in the same manner but initialized differently.

One type of exception is used to propagate status values associated with operating system signals and exceptions raised by the RPC run-time primitives. For each status value, an exception has been predefined (for example, exception rpc_x_no_memory is defined for status rpc_s_no_memory); these are declared in the trpcsts.h header file. While not necessary (since the status exceptions are predefined), a status exception can be declared by the application and initialized with the exc_set_status() macro which takes a pointer to the EXCEPTION to be initialized, and the status value. The status value associated with a status exception can be retrieved using the exc_get_status() macro. It takes a pointer to the EXCEPTION and a pointer to the variable in which the status value is to be returned; the value of the macro is 0 if it is a status exception, and -1 otherwise.

The second type of exception is used to define application exceptions. It is initialized by calling the EXCEPTION_INIT() macro. The address of the exception is stored as the value within the address exception. Note that this value is valid only within a single address space and will change if the exception is an automatic variable. For this reason,

an address exception should be declared as a static or external variable, not an automatic or register variable. The exc_get_status() macro will evaluate to -1 for an address exception. Using the exc_set_status() macro on this exception will make it a status exception.

The exc_matches macro can be used to compare two exceptions. To compare equal, the exceptions must both be the same type and have the same value (for example, the same status value for status exceptions, or the same addresses for address exceptions). This comparison is used for the CATCH clause, described above.

When status exceptions are raised, a common part of handling the exception might be to print out the status value, or better yet, a string indicating what status value occurred. If the string is to be printed to the standard error output, then the function <code>exc_report()</code> can be called with a pointer to the <code>status</code> exception to print the string in one operation.

```
CATCH_ALL
{
   exc_report(THIS_CATCH);
}
ENDTRY
```

If something else is to be done with the string (for example, printing the error to the user log), exc_get_status() can be used on THIS_CATCH to get the status value (remember that THIS_CATCH is already a pointer to an EXCEPTION, not an EXCEPTION), and dce_error_inq_text() can be used to get the string value associated with the status value.

```
CATCH_ALL
{
  unsigned long status_to_convert;
  unsigned char error_text[200];
  int status;

  exc_get_status(THIS_CATCH, status_to_convert);
  dce_error_inq_text(status_to_convert, error_text, status);
  userlog("%s", (char *)error_text);
}
ENDTRY
```

Note: A thread in a multithreaded application may invoke the TRY/CATCH interface while running in any context state, including TPINVALIDCONTEXT.

When to Use Exception and Status Returns The status of RPC operations can be determined portably by defining status variables for each operation ([comm_status] and [fault_status] parameters are defined via the Attribute Configuration File). The status-returning interface is the only interface provided in the X/OPEN RPC specification. The fault_status attribute indicates that errors occurring on the server due to incorrectly specified parameter values, resource constraints, or coding errors be reported by an additional status argument or return value. Similarly, the comm_status attribute indicates that RPC communications failures be reported by an additional status argument or return value. Using status values works well for fine-grained error handling (on a per-call basis) with recovery specified for each possible error on each call, and where it is necessary to retry from the point of failure. The disadvantage is that it is not transparent whether or not the call is local or remote. The remote call has additional status parameters, or a status return value instead of being a void return. Thus, the application must have procedure declarations adjusted between local and distributed code.

For application portability from an OSF/DCE environment, the TRY/CATCH exception-returning interface is also provided. This interface may not be provided in all environments. However, it has the advantage that procedure declarations need not be adjusted between local and distributed code, maintaining existing interfaces. The checking for errors can be simplified such that each procedure call does not have specific failure checking or recovery code. If an error is not handled at some level, then the program exits with a system error message such that the error is detected and can be corrected (omissions become more obvious). Exceptions work better for coarse-grained exception handling.

Built-in Exceptions

The exceptions shown in Table 13 are "built-in" to the use of this exception interface. The first TRY clause sets up a signal handler to catch the signals list below if they are not currently ignored or caught; the other exceptions are defined only for DCE program portability.

Table 13 Built-in Exceptions

Exception	Description
exc_e_SIGBUS	An unhandled SIGBUS signal occurred.
exc_e_SIGEMT	An unhandled SIGEMT signal occurred.
exc_e_SIGFPE	An unhandled SIGFPE signal occurred.
exc_e_SIGILL	An unhandled SIGILL signal occurred.
exc_e_SIGIOT	An unhandled SIGIOT signal occurred.

Table 13 Built-in Exceptions (Continued)

Exception	Description
exc_e_SIGPIPE	An unhandled SIGPIPE signal occurred.
exc_e_SIGSEGV An unhandled SIGSEGV signal occurred.	
exc_e_SIGSYS	An unhandled SIGSYS signal occurred.
exc_e_SIGTRAP An unhandled SIGTRAP signal occurred.	
exc_e_SIGXCPU	An unhandled SIGXCPU signal occurred.
exc_e_SIGXFSZ	An unhandled SIGXFSZ signal occurred.
pthread_e_badparam	
pthread_e_defer_q_full	
pthread_e_existence	
pthread_e_in_use	
pthread_e_nostackmem	
pthread_e_nostack	
pthread_e_signal_q_full	
pthread_e_stackovf	
pthread_e_unimp	
pthread_e_use_error	
exc_e_decovf	
exc_e_exquota	
exc_e_fltdiv	
exc_e_fltovf	
exc_e_fltund	
exc_e_illaddr	
exc_e_insfmem	

Table 13 Built-in Exceptions (Continued)

Exception	Description
exc_e_intdiv	
exc_e_intovf	
exc_e_nopriv	
exc_e_privinst	
exc_e_resaddr	
exc_e_resoper	
exc_e_subrng	
exc_e_uninitexc	

These same exception codes are also defined with the "_e" at the end of the name (for example, exc_e_SIGBUS is also defined as exc_SIGBUS_e). Equivalent status codes are defined with similar names but the "_e_" is changed to "_s_" (for example, exc_e_SIGBUS is equivalent to the exc_s_SIGBUS status code).

Caveats

In OSF/DCE, the header file is named <code>exc_handling.h</code>; the BEA Tuxedo ATMI system header file is <code>texc.h</code>. It is not possible for the same source file to use both DCE and BEA Tuxedo ATMI system exception handling. Further, within a program, the handling of signal exceptions can only be done by either DCE or the BEA Tuxedo ATMI system, not both. See *Programming BEA Tuxedo ATMI Applications Using TxRPC* for a discussion of integrating BEA Tuxedo ATMI System/TxRPC stubs and OSF/DCE stubs in a single program.

When linking a program using this interface, \$TUXDIR/lib/libtrpc.a must be included.

Examples The following is an example C source file that uses exceptions:

```
/* exception - open() failed */
  CATCH (badopen e)
     fprintf(stderr, "Cannot open %s\en", filename);
                                          /* handle other errors */
    /* handle rpc service not available, ... */
    exc report(THIS CATCH)
  ENDTRY
/*
 * Open output file
* Get the remote data item
 * Write out to file
* /
get and update data(char *filename)
 FILE *fp;
 if ((fp == fopen(filename)) == NULL) /* open output file */
   RAISE (badopen e);
                                /* raise exception */
   /* in this block, file is opened successfully -
     * use associated FINALLY to close file
    */
     long data;
      * Execute RPC call - exceptions are raised to the calling
      * function, doit()
      * /
      data = remote get data();
      fprintf(fp, "%ld\en", data);
   /* Whether or not exceptions are raised, close the file */
     fclose(fp);
  ENDTRY
     See Also
             tidl(1), userlog(3c)
              abort(2) in a UNIX system reference manual
```

Programming BEA Tuxedo ATMI Applications Using TxRPC

tuxgetenv(3c)

Portability

Name tuxgetenv()—Returns value for environment name.

Synopsis #include <atmi.h>

char *tuxgetenv(char *name)

Description tuxgetenv() searches the environment list for a string of the form name=value and,

if the string is present, returns a pointer to the *value* in the current environment.

Otherwise, it returns a NULL pointer.

This function provides a portable interface to environment variables across the different platforms on which the BEA Tuxedo ATMI system is supported, including those platforms that do not normally have environment variables.

Note that tuxgetenv is case-sensitive.

A thread in a multithreaded application may issue a call to tuxgetenv() while running in any context state, including TPINVALIDCONTEXT.

Return Values If a pointer to the string exists, tuxgetenv() returns that pointer. If a pointer does not exist, tuxgetenv() returns a NULL pointer.

On MS Windows, this function overcomes the inability to share environment variables between an application and a Dynamic Link Library. The BEA Tuxedo ATMI Workstation DLL maintains an environment copy for each application that is attached to it. This associated environment and context information is destroyed when tpterm() is called from a Windows application. The value of an environment variable could be changed after the application program calls tpterm().

It is recommended that uppercase variable names be used for the DOS, Windows, OS/2, and NetWare environments. (tuxreadenv() converts all environment variable names to uppercase.)

See Also tuxputenv(3c), tuxreadenv(3c)

tuxgetmbaconv(3c)

Name tuxgetmbaconv()—Gets the value for environment variable TPMBACONV in the

process environment.

Synopsis #include <atmi.h>

extern int tperrno;

int

tuxgetmbaconv(long flags) /* Get TPMBACONV info */

Description This function is used for getting the TPMBACONV status. The tuxgetnombaconv()

function is used by an application developer to check if the automatic conversion capability of the typed switch buffers is turned off. By default the TPMBACONV is

not set and automatic conversion functions are used.

The *flags* argument is not currently used and should be set to 0.

Return Values tuxgetnombaconv() returns MBAUTOCONVERSION ON if the TPMBACONV

is set and MBAUTOCONVERSION OFF if TPMBACONV is not set.

See Also tuxgetenv(3c), tuxsetmbaconv(3c)

tuxgetmbenc(3c)

Name tuxgetmbenc()—Gets the code-set encoding name for environment variable

TPMBENC in the process environment.

Synopsis #include <atmi.h>

extern int tperrno;

int

tuxgetmbenc(char *enc name, long flags)

Description

This function is used for getting the codeset encoding name that is contained in the TPMBENC environment variable. This environment variable is automatically used as the default codeset encoding name when an MBSTRING typed buffer is created. The default encoding name can be reset or unset using the tpsetmbenc() function once the new message is available.

The enc_name argument will contain the value of the TPMBENC environment variable upon successful execution of this function. This pointer should be large enough for the encoding name to be copied into.

The *flags* argument is not currently used and should be set to 0.

Return Values

Upon success, tuxgetmbenc() returns 0; otherwise, it returns a non-zero value on error.

See Also

tpconvmb(3c), tpgetmbenc(3c), tpsetmbenc(3c), tuxgetenv(3c),

tuxsetmbenc(3c)

tuxputenv(3c)

Name tuxputenv()—Changes or adds a value to the environment.

Synopsis #include <atmi.h>

int tuxputenv(char *string)

Description

string points to a string of the form "name=value." tuxputenv() makes the value of the environment variable name equal to value by altering an existing variable or creating a new one. In either case, the string pointed to by string becomes part of the environment

This function provides a portable interface to environment variables across the different platforms on which the BEA Tuxedo ATMI system is supported, including those platforms that do not normally have environment variables.

Note that tuxputenv() is case-sensitive.

A thread in a multithreaded application may issue a call to tuxputenv() while running in any context state, including TPINVALIDCONTEXT.

Return Values

If tuxputenv() cannot obtain enough space, via malloc(), for an expanded environment, it returns a non-zero integer. Otherwise, it returns zero.

Portability

On MS Windows, this function overcomes the inability to share environment variables between an application and a Dynamic Link Library. The BEA Tuxedo ATMI system Workstation DLL maintains an environment copy for each application that is attached to it. This associated environment and context information is destroyed when tpterm() is called from a Windows application. The value of an environment variable could be changed after the application program calls tpterm().

We recommend using uppercase variable names for the DOS, Windows, and OS/2, environments. (tuxreadenv() converts all environment variable names to uppercase.)

See Also tuxgetenv(3c), tuxreadenv(3c)

tuxreadenv(3c)

Name tuxreadeny()—Adds variables to the environment from a file.

Synopsis #include <atmi.h>
 int tuxreadenv(char *file, char *label)

Description

tuxreadenv() reads a file containing environment variables and adds them to the environment, independent of platform. These variables are available using tuxgetenv() and can be reset using tuxputenv().

The format of the environment file is as follows:

- Any leading space or tab character on a line is ignored and is not considered in the following points.
- Lines containing variables to be put into the environment are of the form:

variable=value

or
set variable=value

where *variable* must begin with an alphabetic or underscore character and contain only alphanumeric or underscore characters, and *value* may contain any character except newline.

- Within the value, strings of the form \${env}\$ are expanded using variables already in the environment (forward referencing is not supported and if a value is not set, the variable is replaced with the empty string). Backslash (\) may be used to escape the dollar sign and itself. All other shell quoting and escape mechanisms are ignored and the expanded value is placed into the environment.
- Lines beginning with slash (/), pound sign (#), semicolon (;), or exclamation point (!) are treated as comments and ignored. Lines beginning with other characters besides these comment characters, a left square bracket, or an alphabetic or underscore character are reserved for future use; their use is undefined.

■ The file is partitioned into sections by lines beginning with left square bracket ([), which acts as a label. The label will be silently truncated if longer than 31 characters. The format of a label is:

```
[label]
```

where label follows the same rules for variable above (lines with invalid label values are ignored).

■ Variable lines between the top of the file and the first label are put into the environment for all labels (this is the global section). Other variables are put into the environment only if the label matches the label specified for the application. A label of [] will indicate the global section.

If file is NULL, then a default filename is used. The fixed filenames are as follows:

```
DOS, Windows, OS2, NT: C:\TUXEDO\TUXEDO.ENV
MAC: TUXEDO.ENV in the system preferences directory
NETWARE: SYS:SYSTEM\TUXEDO.ENV
POSIX: /usr/tuxedo/TUXEDO.ENV Or /var/opt/tuxedo/TUXEDO.ENV
```

If <code>label</code> is NULL, then only variables in the global section are put into the environment. For other values of <code>label</code>, the global section variables plus any variables in a section matching the <code>label</code> are put into the environment.

An error message is printed to the userlog() if there is a memory failure, if a non-NULL filename does not exist, or if a non-NULL label does not exist.

A thread in a multithreaded application may issue a call to tuxreadenv() while running in any context state, including TPINVALIDCONTEXT.

Example The following is an example environment file.

```
TUXDIR=/usr/tuxedo
[application1]
;this is a comment
/* this is a comment */
#this is a comment
//this is a comment
FIELDTBLS=app1_flds
FLDTBLDIR=/usr/app1/udataobj
[application2]
FIELDTBLS=app2_flds
FLDTBLDIR=/usr/app2/udataobj
```

Section 3c - C Functions

Return Values If tuxreadenv() cannot obtain enough space, via malloc(), for an expanded

environment, or if it cannot open and read a file with a non-NULL name, it returns a

non-zero integer. Otherwise, tuxreadenv() returns zero.

Portability In the DOS, Windows, OS/2, and NetWare environments, tuxreadenv() converts all

environment variable names to uppercase.

See Also tuxgetenv(3c), tuxputenv(3c)

tuxsetmbaconv(3c)

Name tuxsetmbaconv()—Sets the value for environment variable TPMBACONV in the

process environment.

Synopsis #include <atmi.h>

extern int tperrno;

int

tuxsetmbaconv(int onoff, long flags) /* Set TPMBACONV */

Description This function is used for setting or resetting the TPMBACONV environment variable.

By default TPMBACONV is not set and automatic conversion functions are used.

The *onoff* argument is equal to MBAUTOCONVERSION_OFF to unset TPMBACONV and turn off auto-conversions. It is equal to

MBAUTOCONVERSION ON to set TPMBACONV and turn on the typed switch

buffers auto-conversion of codeset multi-byte data.

The *flags* argument is not currently used and should be set to 0.

Return Values Upon success, tuxsetnombaconv() returns 0; otherwise, it returns a non-zero value on

error. (e.g. it returns -1 if the onoff arg is not one of the defined values).

See Also tuxgetmbaconv(3c), tuxputenv(3c)

tuxsetmbenc(3c)

Name tuxsetmbenc()—Sets the code-set encoding name for environment variable

TPMBENC in the process environment.

Synopsis #include <atmi.h>

extern int tperrno;

tuxsetmbenc(char *enc name, long flags)

Description This function is used for setting or resetting the codeset encoding name that is

> contained in the TPMBENC environment variable. This environment variable is automatically used as the default codeset encoding name when an MBSTRING typed

buffer is created. This default encoding name can be reset or unset using the

tpsetmbenc() function once the new message is available.

The enc name argument is the encoding name to use to identify the codeset.

The *flags* argument is not currently used and should be set to 0.

Return Values Upon success, tuxsetmbenc() returns 0; otherwise, it returns a non-zero value on error.

See Also tpconvmb(3c), tpgetmbenc(3c), tpsetmbenc(3c), tuxgetmbenc(3c),

tuxputenv(3c)

tx_begin(3c)

Name tx begin()—Begins a global transaction.

Synopsis #include <tx.h>
 int tx_begin(void)

Description tx_begin() is used to place the calling thread of control in transaction mode. The calling thread must first ensure that its linked resource managers have been opened (via tx open()) before it can start transactions. tx begin() fails (returning

 $\label{thm:caller} \begin{tabular}{ll} $[{\tt TX_PROTOCOL_ERROR}]$) if the caller is already in transaction mode or ${\tt tx_open()}$ has not been called \\ \end{tabular}$

Once in transaction mode, the calling thread must call $tx_commit()$ or $tx_rollback()$ to complete its current transaction. There are certain cases related to transaction chaining where $tx_begin()$ does not need to be called explicitly to start a transaction. See $tx_commit()$ and $tx_rollback()$ for details.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tx begin().

Optional Set-up tx_set_transaction_timeout()

Return Value Upon successful completion, tx begin() returns TX OK, a non-negative return value.

Errors Under the following conditions, tx_begin() fails and returns one of these negative values:

[TX OUTSIDE]

The transaction manager is unable to start a global transaction because the calling thread of control is currently participating in work outside any global transaction with one or more resource managers. All such work must be completed before a global transaction can be started. The caller's state with respect to the local transaction is unchanged.

[TX_PROTOCOL ERROR]

The function was called in an improper context (for example, the caller is already in transaction mode). The caller's state with respect to transaction mode is unchanged.

[TX_ERROR]

Either the transaction manager or one or more of the resource managers encountered a transient error trying to start a new transaction. When this error

is returned, the caller is not in transaction mode. The exact nature of the error is written to a log file.

[TX_FAIL]

Either the transaction manager or one or more of the resource managers encountered a fatal error. The nature of the error is such that the transaction manager and/or one or more of the resource managers can no longer perform work on behalf of the application. When this error is returned, the caller is not in transaction mode. The exact nature of the error is written to a log file.

Warnings XA-compliant resource managers must be successfully opened to be included in the global transaction. (See tx_open(3c) for details.) Both the X/Open TX interface and the X-Windows system define the type XID. It is not possible to use both X-Windows calls and TX calls in the same file.

tx_close(3c)

Name tx close()—Closes a set of resource managers.

Synopsis #include <tx.h>
 int tx close(void)

Description tx_close() closes a set of resource managers in a portable manner. It invokes a transaction manager to read resource-manager-specific information in a transaction-manager-specific manner and pass this information to the resource managers linked to the caller.

tx_close() closes all resource managers to which the caller is linked. This function is used in place of resource-manager-specific "close" calls and allows an application program to be free of calls which may hinder portability. Since resource managers differ in their termination semantics, the specific information needed to "close" a particular resource manager must be published by each resource manager.

<code>tx_close()</code> should be called when an application thread of control no longer wishes to participate in global transactions. $tx_close()$ fails (returning <code>[TX_PROTOCOL_ERROR]</code>) if the caller is in transaction mode. That is, no resource managers are closed even though some may not be participating in the current transaction.

When $tx_close()$ returns success (TX_OK), all resource managers linked to the calling thread are closed.

In a multithreaded application, a thread in the $\mathtt{TPINVALIDCONTEXT}$ state is not allowed to issue a call to \mathtt{tx} close().

Return Value Upon successful completion, tx_close() returns TX_OK, a non-negative return value.

Under the following conditions, tx_close() fails and returns one of these negative values:

[TX_PROTOCOL ERROR]

The function was called in an improper context (for example, the caller is in transaction mode). No resource managers are closed.

[TX_ERROR]

Errors

Either the transaction manager or one or more of the resource managers encountered a transient error. The exact nature of the error is written to a log file. All resource managers that could be closed are closed.

[TX_FAIL]

Either the transaction manager or one or more of the resource managers encountered a fatal error. The nature of the error is such that the transaction manager and/or one or more of the resource managers can no longer perform work on behalf of the application. The exact nature of the error is written to a log file.

See Also tx open(3c)

 $\label{prop:continuous} Warnings \qquad Both the \ X/Open \ TX \ interface \ and the \ X-Windows \ system \ define \ the \ type \ XID. \ It \ is$

not possible to use both X-Windows calls and TX calls in the same file.

tx_commit(3c)

Name tx commit()—Commits a global transaction.

Synopsis #include <tx.h>
 int tx_commit(void)

Description tx_commit() is used to commit the work of the transaction active in the caller's thread of control

If the transaction control characteristic (see

returns, the caller remains in transaction mode on behalf of a new transaction (see the Return Value and Errors sections below).

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tx commit().

Optional Set-up

- tx set commit return()
- tx_set_transaction_control()
- tx set transaction timeout()

Return Value

Upon successful completion, $tx_commit()$ returns TX_OK , a non-negative return value.

Frrors

Under the following conditions, tx_commit() fails and returns one of these negative values:

```
[TX NO BEGIN]
```

The current transaction committed successfully; however, a new transaction could not be started and the caller is no longer in transaction mode. This return value may occur only when the <code>transaction_control</code> characteristic is <code>TX CHAINED</code>.

[TX_ROLLBACK]

The current transaction could not commit and has been rolled back. In addition, if the transaction_control characteristic is TX_CHAINED, a new transaction is started.

[TX ROLLBACK NO BEGIN]

The transaction could not commit and has been rolled back. In addition, a new transaction could not be started and the caller is no longer in transaction mode. This return value can occur only when the <code>transaction_control</code> characteristic is <code>TX CHAINED</code>.

[TX MIXED]

The work done on behalf of the transaction was partially committed and partially rolled back. In addition, if the transaction_control characteristic is TX CHAINED, a new transaction is started.

[TX MIXED NO BEGIN]

The work done on behalf of the transaction was partially committed and partially rolled back. In addition, a new transaction could not be started and the caller is no longer in transaction mode. This return value can occur only when the *transaction control* characteristic is TX CHAINED.

[TX HAZARD]

Due to a failure, some of the work done on behalf of the transaction may have been committed and some of it may have been rolled back. In addition, if the <code>transaction_control</code> characteristic is <code>TX_CHAINED</code>, a new transaction is started.

[TX HAZARD NO BEGIN]

Due to a failure, some of the work done on behalf of the transaction may have been committed and some of it may have been rolled back. In addition, a new transaction could not be started and the caller is no longer in transaction mode. This return value can occur only when the <code>transaction_control</code> characteristic is <code>TX CHAINED</code>.

[TX_PROTOCOL_ERROR]

The function was called in an improper context (for example, the caller is not in transaction mode). The caller's state with respect to transaction mode is not changed.

[TX_FAIL]

Either the transaction manager or one or more of the resource managers encountered a fatal error. The nature of the error is such that the transaction manager and/or one or more of the resource managers can no longer perform work on behalf of the application. The exact nature of the error is written to a log file. The caller's state with respect to the transaction is unknown.

Introduction to the C Language Application-to-Transaction Monitor Interface

Warnings Both the X/Open TX interface and the X-Windows system define the type XID. It is not possible to use both X-Windows calls and TX calls in the same file.

tx_info(3c)

Name tx info()—Returns global transaction information.

Synopsis #include <tx.h>

int tx info(TXINFO *info)

Description

<code>tx_info()</code> returns global transaction information in the structure pointed to by <code>info</code>. In addition, this function returns a value indicating whether the caller is currently in transaction mode or not. If <code>info</code> is non-NULL, then <code>tx_info()</code> populates a <code>TXINFO</code> structure pointed to by <code>info</code> with global transaction information. The <code>TXINFO</code> structure contains the following elements:

XID xid;
COMMIT_RETURN when_return;
TRANSACTION_CONTROL transaction_control;
TRANSACTION_TIMEOUT transaction_timeout;
TRANSACTION STATE transaction state;

If tx_info() is called in transaction mode, then xid will be populated with a current transaction branch identifier and transaction_state will contain the state of the current transaction. If the caller is not in transaction mode, xid will be populated with the NULL XID (see the tx.h file for details). In addition, regardless of whether the caller is in transaction mode, when_return, transaction_control, and transaction_timeout contain the current settings of the commit_return and transaction_control characteristics, and the transaction timeout value in seconds.

The transaction timeout value returned reflects the setting that will be used when the next transaction is started. Thus, it may not reflect the timeout value for the caller's current global transaction since calls made to tx_set_transaction_timeout() after the current transaction was begun may have changed its value.

If *info* is NULL, no TXINFO structure is returned.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tx info().

Return Value

If the caller is in transaction mode, then 1 is returned. If the caller is not in transaction mode, then 0 is returned.

Errors

Under the following conditions, tx_info() fails and returns one of these negative values:

```
[TX PROTOCOL ERROR]
```

The function was called in an improper context (for example, the caller has not yet called tx open()).

```
[TX FAIL]
```

The transaction manager encountered a fatal error. The nature of the error is such that the transaction manager can no longer perform work on behalf of the application. The exact nature of the error is written to a log file.

Warnings Within the same global transaction, subsequent calls to tx_info() are guaranteed to provide an XID with the same gtrid component, but not necessarily the same bqual component. Both the X/Open TX interface and the X-Windows system define the type XID. It is not possible to use both X-Windows calls and TX calls in the same file.

tx_open(3c)

Name tx open()—Opens a set of resource managers.

Synopsis #include <tx.h>
 int tx open(void)

Description

tx_open() opens a set of resource managers in a portable manner. It invokes a transaction manager to read resource-manager-specific information in a transaction-manager-specific manner and pass this information to the resource managers linked to the caller.

tx_open() attempts to open all resource managers that have been linked with the application. This function is used in place of resource-manager-specific "open" calls and allows an application program to be free of calls which may hinder portability. Since resource managers differ in their initialization semantics, the specific information needed to "open" a particular resource manager must be published by each resource manager.

If $tx_open()$ returns TX_ERROR , then no resource managers are open. If $tx_open()$ returns TX_OK , some or all of the resource managers have been opened. Resource managers that are not open will return resource-manager-specific errors when accessed by the application. $tx_open()$ must successfully return before a thread of control participates in global transactions.

Once $tx_{open()}$ returns success, subsequent calls to $tx_{open()}$ (before an intervening call to $tx_{olose()}$) are allowed. However, such subsequent calls will return success, and the TM will not attempt to reopen any RMs.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tx open().

Return Value

Upon successful completion, tx open() returns TX OK, a non-negative return value.

Errors

Under the following conditions, tx_open() fails and returns one of these negative values:

[TX_ERROR]

Either the transaction manager or one or more of the resource managers encountered a transient error. No resource managers are open. The exact nature of the error is written to a log file.

[TX FAIL]

Either the transaction manager or one or more of the resource managers encountered a fatal error. \texttt{TX}_{FAIL} is returned if tpinit() is not called before the call to \texttt{tx}_{open} in a secure application (SECURITY APP_PW). The nature of the error is such that the transaction manager and/or one or more of the resource managers can no longer perform work on behalf of the application. The exact nature of the error is written to a log file.

See Also tx close(3c)

Warnings Both the X/Open TX interface and the X-Windows system define the type XID. It is not possible to use both X-Windows calls and TX calls in the same file.

tx_rollback(3c)

Name tx rollback()—Rolls back a global transaction.

Synopsis #include <tx.h>
 int tx rollback(void)

Description tx_rollback() is used to roll back the work of the transaction active in the caller's thread of control

If the transaction control characteristic (see

tx_set_transaction_control(3c)) is TX_UNCHAINED, then when tx_rollback() returns, the caller is no longer in transaction mode. However, if the transaction_control characteristic is TX_CHAINED, then when tx_rollback() returns, the caller remains in transaction mode on behalf of a new transaction (see the Return Value and Errors sections below).

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tx rollback().

Optional Set-up

- tx set transaction control()
- tx_set_transaction_timeout()

Return Value

Upon successful completion, tx_rollback() returns TX_OK, a non-negative return value.

Errors

Under the following conditions, $tx_rollback()$ fails and returns one of these negative values:

```
[TX NO BEGIN]
```

The current transaction rolled back; however, a new transaction could not be started and the caller is no longer in transaction mode. This return value may occur only when the transaction control characteristic is TX CHAINED.

[TX MIXED]

The work done on behalf of the transaction was partially committed and partially rolled back. In addition, if the transaction_control characteristic is TX_CHAINED, a new transaction is started.

```
[TX MIXED NO BEGIN]
```

The work done on behalf of the transaction was partially committed and partially rolled back. In addition, a new transaction could not be started and the caller is no longer in transaction mode. This return value can occur only when the *transaction control* characteristic is TX CHAINED.

```
[TX HAZARD]
```

Due to a failure, some of the work done on behalf of the transaction may have been committed and some of it may have been rolled back. In addition, if the <code>transaction_control</code> characteristic is <code>TX_CHAINED</code>, a new transaction is started.

```
[TX HAZARD NO BEGIN]
```

Due to a failure, some of the work done on behalf of the transaction may have been committed and some of it may have been rolled back. In addition, a new transaction could not be started and the caller is no longer in transaction mode. This return value can occur only when the <code>transaction_control</code> characteristic is <code>TX CHAINED</code>.

```
[TX COMMITTED]
```

The work done on behalf of the transaction was heuristically committed. In addition, if the transaction_control characteristic is TX_CHAINED, a new transaction is started

```
[TX COMMITTED NO BEGIN]
```

The work done on behalf of the transaction was heuristically committed. In addition, a new transaction could not be started and the caller is no longer in transaction mode. This return value can occur only when the transaction control characteristic is TX CHAINED.

```
[TX_PROTOCOL_ERROR]
```

The function was called in an improper context (for example, the caller is not in transaction mode).

```
[TX_FAIL]
```

Either the transaction manager or one or more of the resource managers encountered a fatal error. The nature of the error is such that the transaction manager and/or one or more of the resource managers can no longer perform work on behalf of the application. The exact nature of the error is written to a log file. The caller's state with respect to the transaction is unknown.

Warnings Both the X/Open TX interface and the X-Windows system define the type XID. It is not possible to use both X-Windows calls and TX calls in the same file.

tx_set_commit_return(3c)

Name tx set commit return()—Sets the commit return characteristic.

Synopsis #include <tx.h>

int tx set commit return (COMMIT RETURN when return)

Description

tx_set_commit_return() sets the commit_return characteristic to the value specified in when_return. This characteristic affects the way tx_commit() behaves with respect to returning control to its caller. tx_set_commit_return() may be called regardless of whether its caller is in transaction mode. This setting remains in effect until changed by a subsequent call to tx_set_commit_return().

The initial setting for this characteristic is TX COMMIT COMPLETED.

The following are the valid settings for when return:

```
TX COMMIT DECISION LOGGED
```

This flag indicates that $tx_commit()$ should return after the commit decision has been logged by the first phase of the two-phase commit protocol but before the second phase has completed. This setting allows for faster response to the caller of $tx_commit()$. However, there is a risk that a transaction will have a heuristic outcome, in which case the caller will not find out about this situation via return codes from $tx_commit()$. Under normal conditions, participants that promise to commit during the first phase will do so during the second phase. In certain unusual circumstances however (for example, long-lasting network or node failures), phase 2 completion may not be possible and heuristic results may occur.

```
TX COMMIT COMPLETED
```

This flag indicates that tx_commit() should return after the two-phase commit protocol has finished completely. This setting allows the caller of tx_commit() to see return codes that indicate that a transaction had or may have had heuristic results.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tx set commit return().

Return Value

Upon successful completion, $tx_set_commit_return()$ returns TX_OK , a non-negative return value.

Errors

Under the following conditions, tx_set_commit_return() does not change the setting of the *commit return* characteristic and returns one of these negative values:

Introduction to the C Language Application-to-Transaction Monitor Interface

[TX EINVAL]

when_return is not one of TX_COMMIT_DECISION_LOGGED or
TX COMMIT COMPLETED.

[TX PROTOCOL ERROR]

The function was called in an improper context (for example, the caller has not yet called tx open()).

[TX FAIL]

The transaction manager encountered a fatal error. The nature of the error is such that the transaction manager can no longer perform work on behalf of the application. The exact nature of the error is written to a log file.

See Also tx_commit(3c), tx_info(3c), tx_open(3c)

Warnings Both the X/Open TX interface and the X-Windows system define the type XID. It is not possible to use both X-Windows calls and TX calls in the same file.

tx_set_transaction_control(3c)

Name tx set transaction control()—Sets the transaction control

characteristic.

Synopsis #include <tx.h>

int tx set transaction control(TRANSACTION CONTROL control)

Description tx set transaction control() sets the transaction control characteristic to

the value specified in <code>control</code>. This characteristic determines whether <code>tx_commit()</code> and <code>tx_rollback()</code> start a new transaction before returning to their caller.

<code>tx set transaction control()</code> may be called regardless of whether the

application program is in transaction mode. This setting remains in effect until changed by a subsequent call to tx set transaction control().

The initial setting for this characteristic is TX UNCHAINED.

The following are the valid settings for control:

TX UNCHAINED

This flag indicates that $tx_commit()$ and $tx_rollback()$ should not start a new transaction before returning to their caller. The caller must issue tx begin() to start a new transaction.

TX CHAINED

This flag indicates that tx_commit() and tx_rollback() should start a new transaction before returning to their caller.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tx set transaction control().

Return Value

Upon successful completion, tx_set_transaction_control() returns TX_OK, a non-negative return value.

Errors

Under the following conditions, tx_set_transaction_control() does not change the setting of the transaction_control characteristic and returns one of these negative values:

[TX_EINVAL]

control is not one of TX UNCHAINED or TX CHAINED.

[TX PROTOCOL ERROR]

The function was called in an improper context (for example, the caller has not yet called tx open()).

[TX FAIL]

The transaction manager encountered a fatal error. The nature of the error is such that the transaction manager can no longer perform work on behalf of the application. The exact nature of the error is written to a log file.

See Also tx_begin(3c), tx_commit(3c), tx_info(3c), tx_open(3c), tx_rollback(3c)

Warnings Both the X/Open TX interface and the X-Windows system define the type XID. It is not possible to use both X-Windows calls and TX calls in the same file.

tx_set_transaction_timeout(3c)

Name tx set transaction timeout()—Sets the transaction timeout

characteristic.

Synopsis #include <tx.h>

int tx set transaction timeout(TRANSACTION TIMEOUT timeout)

Description tx_set_transaction_timeout() sets the transaction_timeout characteristic to

the value specified in timeout. This value specifies the time period in which the transaction must complete before becoming susceptible to transaction timeout; that is,

the interval between the AP calling tx begin() and tx commit() or

tx_rollback().tx_set_transaction_timeout() may be called regardless of whether its caller is in transaction mode or not. If tx_set_transaction_timeout() is called in transaction mode, the new timeout value does not take effect until the next transaction

The initial transaction timeout value is 0 (no timeout).

timeout specifies the number of seconds allowed before the transaction becomes susceptible to transaction timeout. It may be set to any value up to the maximum value for a long as defined by the system. A timeout value of zero disables the timeout feature.

In a multithreaded application, a thread in the TPINVALIDCONTEXT state is not allowed to issue a call to tx set transaction timeout().

Return Value

Upon successful completion, tx_set_transaction_timeout() returns TX_OK, a non-negative return value.

Errors

Under the following conditions, tx_set_transaction_timeout() does not change the setting of the transaction_timeout characteristic and returns one of these negative values:

[TX_EINVAL]

The timeout value specified is invalid.

[TX_PROTOCOL_ERROR]

The function was called improperly. For example, it was called before the caller called $tx_open()$.

[TX FAIL]

The transaction manager encountered an error. The nature of the error is such that the transaction manager can no longer perform work on behalf of the application. The exact nature of the error is written to a log file.

See Also tx begin(3c), tx commit(3c), tx info(3c), tx open(3c), tx rollback(3c)

Warnings Both the X/Open TX interface and the X-Windows system define the type XID. It is not possible to use both X-Windows calls and TX calls in the same file.

userlog(3c)

Name userlog()—Writes a message to the BEA Tuxedo ATMI system central event log.

```
Synopsis #include "userlog.h"
    extern char *proc_name;

int userlog (format [ ,arg] . . .)
    char *format;
```

Description

userlog() accepts a printf(3S) style format specification, with a fixed output file—the BEA Tuxedo ATMI system central event log.

The central event log is an ordinary UNIX file whose pathname is composed as follows: If the shell variable <code>ULOGPFX</code> is set, its value is used as the prefix for the filename. If <code>ULOGPFX</code> is not set, <code>ULOG</code> is used. The prefix is determined the first time <code>userlog()</code> is called. Each time <code>userlog()</code> is called the date is determined, and the month, day, and year are concatenated to the prefix as <code>mmddyy</code> to set the name for the file. The first time a process writes to the user log, it first writes an additional message indicating the associated BEA Tuxedo ATMI system version.

The message is then appended to the file. With this scheme, processes that call userlog() on successive days will write into different files.

Messages are appended to the log file with a tag made up of the time (hhmmss), system name, process name, and process ID, thread ID, and context ID of the calling process. The tag is terminated with a colon (:). The name of the process is taken from the pathname of the external variable proc_name. If proc_name has value NULL, the printed name is set to ?proc.

BEA Tuxedo ATMI system-generated error messages in the log file are prefixed by a unique identification string of the form:

```
<catalog>:number>:
```

This string gives the name of the internationalized catalog containing the message string, plus the message number. By convention, BEA Tuxedo ATMI system-generated error messages are used only once, so the string uniquely identifies a location in the source code.

If the last character of the format specification is not a newline character, userlog() appends one.

If the first character of the shell variable $\tt ULOGDEBUG$ is 1 or y, the message sent to $\tt userlog()$ is also written to the standard error of the calling process, using the $\tt fprintf(3S)$ function.

userlog() is used by the BEA Tuxedo ATMI system to record a variety of events.

The userlog mechanism is entirely independent of any database transaction logging mechanism

A thread in a multithreaded application may issue a call to userlog() while running in any context state, including TPINVALIDCONTEXT.

Portability

The userlog() interface is supported on UNIX and MS-DOS operating systems. The system name produced as part of the log message is not available on MS-DOS systems; therefore, the value PC is used as the system name for MS-DOS systems.

Examples

If the variable ULOGPFX is set to /application/logs/log and if the first call to userlog() occurred on 9/7/90, the log file created is named /application/logs/log.090790. If the call:

```
userlog("UNKNOWN USER '%s' (UID=%d)", usrname, UID);
```

is made at 4:22:14pm on the UNIX system file named m1 by the sec program, whose process-id is 23431, and the variable usrname contains the string "sxx", and the variable UID contains the integer 123, the following line appears in the log file:

```
162214.m1!sec.23431: UNKNOWN USER 'sxx' (UID=123)
```

If the message is sent to the central event log while the process is in transaction mode, the user log entry has additional components in the tag. These components consist of the literal gtrid followed by three long hexadecimal integers. The integers uniquely identify the global transaction and make up what is referred to as the global transaction identifier. This identifier is used mainly for administrative purposes, but it does make an appearance in the tag that prefixes the messages in the central event log. If the foregoing message is written to the central event log in transaction mode, the resulting log entry will look like this:

```
162214.logsys!security.23431: gtrid x2 x24e1b803 x239: UNKNOWN USER 'sxx' (UID=123)
```

If the shell variable ULOGDEBUG has a value of y, the log message is also written to the standard error of the program named security.

Errors

userlog() hangs if the message sent to it is larger than BUFSIZ as defined in stdio.h

Diagnostics userlog() returns the number of characters output, or a negative value if an output

error was encountered. Output errors include the inability to open, or write to the current log file. Inability to write to the standard error, when <code>ULOGDEBUG</code> is set, is not

considered an error.

Notices It is recommended that applications' use of userlog() messages be limited to

messages that can be used to help debug application errors; flooding the log with

incidental information can make it hard to spot actual errors.

See Also printf(3S) in a UNIX system reference manual

Usignal(3c)

Name Usignal ()—Signal handling in a BEA Tuxedo ATMI system environment.

Synopsis #include "Usignal.h"

UDEFERSIGS()
UENSURESIGS()
UGDEFERLEVEL()
URESUMESIGS()
USDEFERLEVEL(level)

int (*Usignal(sig,func)()
int sig;
int (*func)();

void Usiginit()

Description

Many of the facilities provided by the BEA Tuxedo ATMI system software require concurrent access to data structures in shared memory. Processes accessing the shared data structures run in user mode, and are thus interruptable by signals sent to them. In order to ensure the consistency of the shared data structures, it is important that the operations which access them not be interrupted by the receipt of certain UNIX signals. The functions described in this section provide protection against the most common signals, and are used internally by much of the BEA Tuxedo ATMI system code. Additionally, they are available to applications to prevent the untimely arrival of a signal.

The idea behind the BEA Tuxedo ATMI system signal handling package is that signals should be deferrable while in critical code sections. To this end, signals are not immediately processed when received. Instead, a BEA Tuxedo ATMI system routine first catches the sent signal. If it is safe to process the signal, the specified action for the signal is taken. If it is not safe to process the signal when it arrives, the arrival is noted, but the processing is deferred until the user indicates that the critical section of code has been terminated.

We recommend against any use of signals in multithreaded programs, although the software does not prevent such usage. If signals are used, however, a thread in a multithreaded application may issue a call to Usignal () while running in any context state, including TPINVALIDCONTEXT.

Catching Signals

User code that uses calls rmopen() or tpinit() should catch signals through the use of the Usignal() function. Usignal() behaves like the UNIX signal() system call, except that Usignal() first arranges for the signal to be caught by an internal routine before dispatching the user routine.

Deferring and Restoring Signals

The calls described in this section need only be used if application code wishes to defer signals. In general, these routines are called automatically by BEA Tuxedo ATMI system routines to protect themselves from untimely signal arrival.

Before deferring or restoring signals, the mechanism must be initialized. This is done automatically for BEA Tuxedo ATMI system clients when they call tpinit() and for BEA Tuxedo ATMI system servers. It is also done the first time that the application calls Usignal(). It can be done explicitly by calling Usignit().

The UDEFERSIGS() macro should be used when entering a section of critical code. After UDEFERSIGS() is called, signals are held in a pending state. The URESUMESIGS() macro should be invoked when the critical section is exited. Note that signal deferrals stack. The stack is implemented via a counter which is initially set to zero. When signals are deferred by a call to UDEFERSIGS(), the counter is incremented. When signals are resumed, by a call to URESUMESIGS(), the counter is decremented. If a signal arrives while the counter is non-zero, the processing of the signal is deferred. If the counter is zero when the signal arrives, the signal is processed immediately. If signal resumption causes the counter to be become zero (that is, prior to the resumption it had value 1), any signals that arrived during the deferral period are processed. In general, each call to UDEFERSIGS() should have a counterpart call to URESUMESIGS().

UDEFERSIGS increments the deferral counter, but returns the value of the counter prior to its incrementation. The macro UENSURESIGS() may be used to explicitly set the deferral counter to zero (and thus force the processing of deferred signals), in case the user wishes to protect against unmatching UDEFERSIGS() and URESUMESIGS().

The function UGDEFERLEVEL() returns the current setting of the deferral counter. The macro USDEFERLEVEL(level) allows the setting of a specific deferral level. UGDEFERLEVEL() and USDEFERLEVEL() are useful to set the counter appropriately in setjmp/longjmp situations where a set of deferrals/resumes are bypassed. The idea is to save the value of the counter when setjmp() is called, via a call to UGDEFERLEVEL(), and to restore it via a call to USDEFERLEVEL() when the longjmp() is performed.

Notices

Usignal provides signal deferral for the following signals: SIGHUP, SIGINT, SIGQUIT, SIGALRM, SIGTERM, SIGUSR1, and SIGUSR2. Handling requests for all other signal numbers are passed directly to signal() by Usignal(). Signals may be deferred for

a considerable time. For this reason, during signal deferral, individual signal arrivals are counted. When it is safe to process a signal that may have arrived many times, the signal's processing routine is iteratively called to process each arrival of the signal. Before each call the default action for the signal is instantiated. The idea is to handle the deferred occurrences of the signal as if they happened in quick succession in safe code

In general, users should not mix calls to signal() and Usignal() for the same signal. The recommended procedure is to go through Usignal(), so that it is always aware of the state of the signal. Sometimes it may be necessary, such as when an application wants to use alarms within BEA Tuxedo ATMI system services. To do this, Usiginit() should be called to initialize the signal deferring mechanism. Then signal() can be called to override the mechanism for the desired signal. To restore the deferring mechanism for the signal, it is necessary to call Usignal() for the signal with SIG_IGN, and then again with the desired signal-handling function.

The shell variable UIMMEDSIGS can be used to override the deferral of signals. If the value of this variable begins with the letter y as in:

```
UIMMEDSIGS=y
```

signals are not intercepted (and thus not deferred) by the Usignal() code. In such a case, a call to Usignal() is passed immediately to signal().

Usignal is not available under DOS operating systems.

```
Files Usignal.h
```

See Also signal(2) in a UNIX system reference manual

Uunix_err(3c)

Name Uunix err()—Prints a UNIX system call error.

```
Synopsis #include Uunix.h

void Uunix_err(s)
char *s;
```

Description

When a BEA Tuxedo ATMI system function calls a UNIX system call that detects an error, an error is returned. The external integer Uunixerr() is set to a value (as defined in Uunix.h) that identifies the system call that returned the error. In addition, the system call sets errno() to a value (as defined in errno.h) that tells why the system call failed.

The Uunix_err() function is provided to produce a message on the standard error output, describing the last system call error encountered during a call to a BEA Tuxedo ATMI system function. It takes one argument, a string. The function prints the argument string, then a colon and a blank, followed by the name of the system call that failed, the reason for failure, and a newline. To be of most use, the argument string should include the name of the program that incurred the error. The system call error number is taken from the external variable Uunixerr(), the reason is taken from error (). Both variables are set when errors occur. They are not cleared when non-erroneous calls are made.

To simplify variant formatting of messages, the array of message strings:

```
extern char *Uunixmsg[];
```

is provided; Uunixerr() can be used as an index into this table to get the name of the system call that failed (without the newline).

A thread in a multithreaded application may issue a call to Uunix_err() while running in any context state, including TPINVALIDCONTEXT.

Examples

```
#include Uunix.h
extern int Uunixerr, errno;
......
if((fd=open("myfile", 3, 0660)) == -1)

{
    Uunixerr = UOPEN;
    Uunix_err("myprog");
```

$Introduction\ to\ the\ C\ Language\ Application-to-Transaction\ Monitor\ Interface$

```
exit(1);
}
```