

Core Services User Guide

Oracle FLEXCUBE Universal Banking

Release 12.0.2.5.2

April 2015

Core Services User Guide
April 2015
Oracle Financial Services Software Limited

Oracle Park

Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:

Phone: +91 22 6718 3000

Fax: +91 22 6718 3001

www.oracle.com/financialservices/

Copyright © 2007, 2015, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

| | |
|---------------------------------------------------------------------------|------------|
| 1. Preface | 1-1 |
| 1.1 Introduction..... | 1-1 |
| 1.2 Audience..... | 1-1 |
| 1.3 Documentation Accessibility | 1-1 |
| 1.4 Organization | 1-1 |
| 1.5 Related Documents | 1-3 |
| 1.6 Glossary of Icons..... | 1-3 |
| 2. Bank Parameters | 2-1 |
| 2.1 Defining Bank Level Parameters | 2-1 |
| 2.1.1 <i>Maintaining Financial Preferences</i> | 2-2 |
| 2.1.2 <i>Generating Automatic Balancing Entries</i> | 2-3 |
| 2.1.3 <i>Maintaining General Preferences</i> | 2-4 |
| 2.1.4 <i>Placing User Restrictions on Data Entry Batches</i> | 2-7 |
| 2.1.5 <i>Specifying UDF Details</i> | 2-11 |
| 2.1.6 <i>Specifying Account Generation Parameters at Bank Level</i> | 2-11 |
| 2.1.7 <i>Defining Bank-wide Preferences</i> | 2-20 |
| 2.1.8 <i>Maintaining FATCA Preferences</i> | 2-28 |
| 3. Ramadan Maintenance | 3-1 |
| 3.1 Introduction..... | 3-1 |
| 3.2 Maintaining Ramadan Day | 3-1 |
| 4. Dealer Maintenance | 4-1 |
| 4.1 Defining Dealer..... | 4-1 |
| 5. Branch Parameters | 5-1 |
| 5.1 Creating Branches..... | 5-1 |
| 5.1.1 <i>System Features</i> | 5-1 |
| 5.1.2 <i>Creating Reporting Structure</i> | 5-2 |
| 5.1.3 <i>Basic Parameters for Branch</i> | 5-2 |
| 5.1.4 <i>Maintaining General Details for Branch</i> | 5-4 |
| 5.1.5 <i>Maintaining Financial Details for Branch</i> | 5-7 |
| 5.1.6 <i>Maintaining Duplication Check Details</i> | 5-12 |
| 5.1.7 <i>Maintaining SWIFT Address for Branch</i> | 5-13 |
| 5.1.8 <i>Defining Account Mask</i> | 5-14 |
| 5.1.9 <i>Maintaining Customer Number Range</i> | 5-15 |
| 5.1.10 <i>Maintaining Global Interdict Functions</i> | 5-17 |
| 5.1.11 <i>Maintaining Preferences</i> | 5-18 |
| 5.1.12 <i>Maintaining LCY Message Preference for Branch</i> | 5-25 |
| 5.1.13 <i>Specifying UDF Details</i> | 5-26 |
| 5.2 Maintaining Tax Cycle | 5-26 |
| 5.2.1 <i>Updating Tax Cycle</i> | 5-27 |
| 5.2.2 <i>Maintaining Tax</i> | 5-27 |
| 5.2.3 <i>Maintaining Clearing Currencies</i> | 5-29 |
| 5.2.4 <i>Account Statement Handoff</i> | 5-29 |
| 5.2.5 <i>Account Statement Generation</i> | 5-29 |
| 5.3 Maintaining Role to Head Mapping at Branch Level | 5-30 |

| | | |
|------------|-----------------------------------------------------------|-------------|
| 5.3.1 | <i>Viewing Accounting Role to Head Mapping Details</i> | 5-31 |
| 6. | Account Branch Transfer | 6-1 |
| 6.1 | Introduction | 6-1 |
| 6.2 | Maintaining Branch Transfer Parameters | 6-1 |
| 6.3 | Transferring Customer Account Branch | 6-2 |
| 6.3.1 | <i>Viewing Account Branch Transfer Details</i> | 6-4 |
| 6.4 | Transferring Account Class | 6-5 |
| 6.5 | Processing Account Branch Transfer | 6-6 |
| 7. | System Dates Maintenance | 7-1 |
| 7.1 | Introduction | 7-1 |
| 7.1.1 | <i>Maintaining Dates Change</i> | 7-2 |
| 8. | Web Service Maintenance | 8-1 |
| 8.1 | Introduction | 8-1 |
| 8.2 | Maintaining Web Service | 8-1 |
| 8.2.1 | <i>Mapping of Web Service</i> | 8-2 |
| 8.2.2 | <i>Web Service Details</i> | 8-3 |
| 8.2.3 | <i>WebService Maintenance</i> | 8-4 |
| 9. | Accounts for Inter-Branch Transactions | 9-1 |
| 9.1 | Defining Accounts for Inter-Branch Transactions | 9-1 |
| 9.1.1 | <i>System Features</i> | 9-2 |
| 9.1.2 | <i>Specifying Customer Accounts</i> | 9-4 |
| 9.2 | Defining Accounts for Inter-Branch Fund Transactions | 9-5 |
| 9.2.1 | <i>Querying on Netting Batch</i> | 9-6 |
| 10. | Currency Maintenance | 10-1 |
| 10.1 | Introduction | 10-1 |
| 10.2 | Maintaining Currency Details | 10-1 |
| 10.2.1 | <i>Indicating Rounding Preferences</i> | 10-6 |
| 10.2.2 | <i>Specifying Amount Format Mask</i> | 10-7 |
| 10.2.3 | <i>Specifying Exchange Rate Limits</i> | 10-8 |
| 10.2.4 | <i>Mapping Currency to Country</i> | 10-8 |
| 10.2.5 | <i>Specifying User Defined Fields</i> | 10-9 |
| 10.2.6 | <i>Annexure</i> | 10-9 |
| 10.2.7 | <i>Specifying Currency Cut-Off Parameters</i> | 10-12 |
| 10.3 | Maintaining Currency Position Details | 10-14 |
| 10.4 | Handling Euro | 10-16 |
| 10.5 | Maintaining Euro Related Information | 10-17 |
| 10.5.1 | <i>Maintaining Currency Details</i> | 10-17 |
| 10.5.2 | <i>Maintaining Conversion GLs</i> | 10-19 |
| 10.5.3 | <i>Implications of Currency Redenomination</i> | 10-19 |
| 10.5.4 | <i>Specifying Preferred ERI Currency for Counterparty</i> | 10-21 |
| 10.5.5 | <i>Specifying Settlement Message Details</i> | 10-22 |
| 10.5.6 | <i>Settlements of Foreign Exchange Deals</i> | 10-22 |
| 10.5.7 | <i>Reports and Advices</i> | 10-22 |
| 10.5.8 | <i>Maintaining Limits Type</i> | 10-23 |
| 10.5.9 | <i>Maintaining Transaction Limits</i> | 10-24 |
| 10.6 | Maintaining Sequence Generation Format | 10-26 |
| 11. | Maintaining Currency Denomination | 11-1 |
| 11.1 | Introduction | 11-1 |
| 11.2 | Maintaining Currency Denomination Details | 11-1 |

| | |
|-----------------------------------------------------------------------|-------------|
| 12. Expressing Amounts in Words | 12-1 |
| 12.1 Introduction..... | 12-1 |
| 13. Defining Currency Pairs | 13-1 |
| 13.1 Introduction..... | 13-1 |
| 13.2 System Features | 13-1 |
| 13.3 Maintaining Parameters for Currency Pair | 13-2 |
| 13.3.1 <i>Specifying Points Multiplier</i> | 13-3 |
| 14. Maintaining Exchange Rates | 14-1 |
| 14.1 Introduction..... | 14-1 |
| 14.1.1 <i>Authorizing Exchange Rates</i> | 14-4 |
| 14.1.2 <i>Revising Exchange Rates</i> | 14-4 |
| 14.1.3 <i>Viewing Exchange Rates</i> | 14-4 |
| 14.1.4 <i>Specifying Limits for Cross Currency Transactions</i> | 14-4 |
| 15. Maintaining Currency Spread for Customer | 15-1 |
| 15.1 Maintaining Customer Spread Details | 15-1 |
| 15.1.1 <i>Computing Buy and Sell Spreads</i> | 15-2 |
| 15.1.2 <i>Maintaining Currency Margins for Customer</i> | 15-2 |
| 16. Period Code Maintenance | 16-1 |
| 16.1 Introduction..... | 16-1 |
| 16.2 Invoking Period Code Maintenance Screen | 16-1 |
| 16.3 System Functions | 16-3 |
| 17. Status Code Maintenance | 17-1 |
| 17.1 Introduction..... | 17-1 |
| 17.2 Invoking Status Maintenance Screen | 17-1 |
| 17.2.1 <i>Maintaining Status Codes for Contracts</i> | 17-2 |
| 17.2.2 <i>Maintaining Status Codes for OD Account</i> | 17-3 |
| 17.3 Maintaining Dormancy Parameter Details | 17-3 |
| 17.4 Maintaining CR\DR Statistics Details | 17-5 |
| 18. Transaction Code Maintenance | 18-1 |
| 18.1 Introduction..... | 18-1 |
| 18.2 Invoking Transaction Code Screen | 18-1 |
| 18.2.1 <i>Maintaining Transaction Details</i> | 18-2 |
| 18.2.2 <i>Maintaining Country Name Details</i> | 18-8 |
| 19. Account Revaluation Maintenance | 19-1 |
| 19.1 Introduction..... | 19-1 |
| 20. Maintaining Branch Holidays | 20-1 |
| 20.1 Introduction..... | 20-1 |
| 20.2 Invoking Local Holiday Screen | 20-1 |
| 20.2.1 <i>Steps to Define Yearly Holidays</i> | 20-2 |
| 20.2.2 <i>Defining Holidays</i> | 20-3 |
| 20.2.3 <i>Annual Holidays</i> | 20-3 |
| 20.2.4 <i>Designating Unexpected Holidays for Branch</i> | 20-3 |
| 21. Maintaining Currency Holidays | 21-1 |
| 21.1 Introduction..... | 21-1 |
| 21.2 Invoking Currency Holiday Screen | 21-1 |
| 21.2.1 <i>Steps to Define Currency Holidays</i> | 21-2 |
| 21.2.2 <i>Defining Currency Holidays</i> | 21-2 |
| 21.3 Uploading Holiday File..... | 21-2 |

| | |
|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------|
| 22. Maintaining Clearing Holidays | 22-1 |
| 22.1 Introduction..... | 22-1 |
| 22.1.1 <i>Steps to Define Clearing House Holidays</i> | 22-1 |
| 22.1.2 <i>Defining Clearing House Holidays</i> | 22-2 |
| 22.1.3 <i>Designating Unexpected Holidays for Clearing House</i> | 22-2 |
| 23. Document Maintenance | 23-1 |
| 23.1 Introduction..... | 23-1 |
| 23.2 Maintaining Document Type..... | 23-1 |
| 23.3 Viewing Document Type Details..... | 23-1 |
| 23.4 Maintaining Document Checklist Details | 23-3 |
| 23.5 Viewing Document Type Details..... | 23-4 |
| 24. Configuring Overrides | 24-1 |
| 24.1 Introduction..... | 24-1 |
| 24.1.1 <i>Types of Overrides</i> | 24-1 |
| 24.2 Specifying Override Type | 24-2 |
| 24.2.1 <i>Maintaining Override Conversion</i> | 24-3 |
| 24.2.2 <i>Maintaining Error Codes</i> | 24-3 |
| 25. Maintaining Features | 25-1 |
| 25.1 Introduction..... | 25-1 |
| 25.2 Maintaining Feature ID | 25-1 |
| 25.2.1 <i>Specifying UDF Values</i> | 25-3 |
| 25.3 Viewing Feature ID Summary..... | 25-3 |
| 26. Purging Data | 26-1 |
| 26.1 Introduction..... | 26-1 |
| 26.2 Module Purging | 26-1 |
| 26.3 The system will automatically purge data according to the parameters that you define in the Purge Details Maintenance screen. Maintaining Purge Details | 26-2 |
| 26.4 Entity Purging | 26-3 |
| 26.4.1 <i>Configuring Purge Parameters</i> | 26-4 |
| 26.4.2 <i>Viewing Purge Parameter Configuration Details</i> | 26-6 |
| 26.4.3 <i>Processing Ad-hoc Purge</i> | 26-7 |
| 26.4.4 <i>Inquiring Purge Log</i> | 26-9 |
| 27. Support 24x7 | 27-1 |
| 27.1 Introduction..... | 27-1 |
| 27.1.1 <i>Gateway Messaging</i> | 27-1 |
| 27.1.2 <i>Web Branch</i> | 27-1 |
| 27.1.3 <i>Batch Processing</i> | 27-1 |
| 27.1.4 <i>Processing Different Categories during EOD</i> | 27-2 |
| 28. Tanking of Maintenance Records | 28-1 |
| 28.1 Introduction..... | 28-1 |
| 28.2 Tanking New and Modified Maintenance Records | 28-1 |
| 28.2.1 <i>Tanking New Records</i> | 28-2 |
| 28.2.2 <i>Tanking Modified Records</i> | 28-2 |
| 28.2.3 <i>Closing a Record</i> | 28-2 |
| 28.2.4 <i>Re-opening a Record</i> | 28-2 |
| 28.2.5 <i>Authorizing a Record</i> | 28-2 |
| 28.2.6 <i>Deleting a Record</i> | 28-2 |
| 28.2.7 <i>Viewing Summary of Records</i> | 28-2 |
| 28.2.8 <i>Modifying Tanking Preferences</i> | 28-2 |

| | |
|--------------------------------------------------------------------|-------------|
| 29. External Deal Maintenance | 29-1 |
| 29.1 Introduction..... | 29-1 |
| 30. Annexure B - File Formats | 30-1 |
| 30.1 Introduction..... | 30-1 |
| 30.2 Upload File Formats | 30-1 |
| 31. Anti-Money Laundering Reporting | 31-1 |
| 31.1 Guarding Against Money Laundering | 31-1 |
| 31.1.1 <i>Creating Product Categories in Oracle FLEXCUBE</i> | 31-1 |
| 31.2 Maintaining Limit Codes | 31-3 |
| 31.3 Maintaining Anti Money Laundering Customer Groups | 31-4 |
| 31.4 Monitoring AML Accounting..... | 31-7 |
| 32. Developer and Developer Project Maintenance | 32-1 |
| 32.1 Introduction..... | 32-1 |
| 32.2 Maintaining Developer Details..... | 32-1 |
| 32.2.1 <i>Viewing Project Details</i> | 32-2 |
| 32.2.2 <i>Viewing UDF Details</i> | 32-3 |
| 32.3 Viewing Developer Maintenance Summary..... | 32-3 |
| 32.4 Maintaining Developer Project Details..... | 32-4 |
| 32.4.1 <i>Viewing UDF Details</i> | 32-5 |
| 32.5 Viewing Developer Project Maintenance Summary | 32-6 |
| 33. Project Financing | 33-1 |
| 33.1 Introduction..... | 33-1 |
| 33.2 Processing Finance for Project..... | 33-1 |
| 33.3 Maintaining Project Financing Transaction..... | 33-4 |
| 33.3.1 <i>Specifying the Project Details</i> | 33-5 |
| 33.3.2 <i>Specifying the Main Details</i> | 33-7 |
| 33.3.3 <i>Specifying Milestones Details</i> | 33-8 |
| 33.3.4 <i>Specifying the Venture Details</i> | 33-9 |
| 33.3.5 <i>Specifying PPC Limits Details</i> | 33-11 |
| 33.3.6 <i>Specifying Non PPC Limits Details</i> | 33-13 |
| 33.4 Maintaining PPC..... | 33-14 |
| 33.4.1 <i>Specifying PPC Maintenance Details</i> | 33-15 |
| 33.4.2 <i>Specifying Joint Venture Details</i> | 33-16 |
| 33.4.3 <i>Maintaining PPC Liquidation</i> | 33-17 |
| 33.5 Viewing Dashboard Details | 33-18 |
| 33.5.1 <i>Viewing PPC Details</i> | 33-18 |
| 33.5.2 <i>Viewing Limit Details</i> | 33-19 |
| 33.5.3 <i>Viewing Commitment Details</i> | 33-20 |
| 33.5.4 <i>Viewing Loan Details</i> | 33-21 |
| 33.6 Querying Dashboard Details | 33-22 |
| 33.7 Querying Accounting Entries | 33-22 |
| 34. Error and Error Codes for Project Financing | 34-1 |
| 34.1 Error and Error Codes | 34-1 |
| 35. Reports | 35-1 |
| 35.1 Introduction..... | 35-1 |
| 35.2 List of Deleted Transactions | 35-1 |
| 35.2.1 <i>Contents of Report</i> | 35-2 |
| 35.3 Accounting Journal | 35-4 |
| 35.3.1 <i>Contents of Report</i> | 35-5 |

| | | |
|------------|----------------------------------------------------|-------------|
| 35.4 | Cash Flow Report..... | 35-6 |
| 35.4.1 | <i>Contents of Report</i> | 35-7 |
| 35.4.2 | <i>Cash Flow (Summary) Report</i> | 35-8 |
| 35.5 | Future Dated Account Balance Report..... | 35-9 |
| 35.5.1 | <i>Contents of the Report</i> | 35-9 |
| 35.6 | Current Rates Report | 35-10 |
| 35.6.1 | <i>Contents of Report</i> | 35-11 |
| 35.7 | Rate History Report | 35-11 |
| 35.8 | Customer Account Opening Confirmation Report | 35-13 |
| 35.8.1 | <i>Contents of the Report</i> | 35-14 |
| 35.9 | Activity Journal Report..... | 35-15 |
| 35.9.1 | <i>Contents of Report</i> | 35-16 |
| 35.10 | Core Exception Report | 35-17 |
| 35.10.1 | <i>Contents of Report</i> | 35-18 |
| 35.11 | Uncollected Funds Report | 35-19 |
| 35.11.1 | <i>Contents of Report</i> | 35-19 |
| 35.12 | Account Revaluation Report..... | 35-20 |
| 35.12.1 | <i>Contents of Report</i> | 35-20 |
| 35.13 | Accounts Movement Report | 35-22 |
| 35.13.1 | <i>Contents of Report</i> | 35-22 |
| 35.14 | Customer Details Report | 35-23 |
| 35.14.1 | <i>Contents of Report</i> | 35-24 |
| 35.15 | Customer Accounts Report | 35-28 |
| 35.15.1 | <i>Contents of Report</i> | 35-29 |
| 35.16 | Document Check List Report..... | 35-31 |
| 35.16.1 | <i>Contents of the Report</i> | 35-33 |
| 35.17 | Memo Revaluation Report..... | 35-34 |
| 35.17.1 | <i>Contents of Report</i> | 35-34 |
| 35.18 | Black Listed During Contract Booking Report | 35-35 |
| 35.18.1 | <i>Contents of the Report</i> | 35-36 |
| 35.19 | Black List Report During File Upload Report..... | 35-37 |
| 35.19.1 | <i>Contents of the Report</i> | 35-37 |
| 35.20 | Cheque Book Issued Report | 35-38 |
| 35.20.1 | <i>Contents of the Report</i> | 35-39 |
| 35.21 | Demand Draft Issued Report..... | 35-39 |
| 35.21.1 | <i>Contents of the Report</i> | 35-40 |
| 35.22 | PDC Input Report | 35-41 |
| 35.22.1 | <i>Contents of the Report</i> | 35-42 |
| 35.23 | Temporary Overdraft Report | 35-43 |
| 35.23.1 | <i>Contents of the Report</i> | 35-44 |
| 35.24 | Daily Sales Report..... | 35-45 |
| 35.24.1 | <i>Contents of the Report</i> | 35-46 |
| 35.25 | Exception Report..... | 35-47 |
| 35.25.1 | <i>Contents of the Events Log</i> | 35-47 |
| 36. | Function ID Glossary | 36-1 |

1. Preface

1.1 Introduction

This manual is designed to help you quickly get acquainted with the Core Services module of Oracle FLEXCUBE.

You can further obtain information specific to a particular field by placing the cursor on the relevant field and striking <F1> on the keyboard.

1.2 Audience

This manual is intended for the following User/User Roles:

| Role | Function |
|---------------------------------------|------------------------------------------------|
| Back office clerk | Input functions for contracts |
| Back office managers/officers | Authorization functions |
| Product Managers | Product definition and authorization |
| End of day operators | Processing during end of day/ beginning of day |
| Financial Controller/Product Managers | Generation of reports |

1.3 Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

1.4 Organization

The manual is organized in the following manner:

| | |
|------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Chapter 1 | <i>About this Manual</i> gives a brief introduction of the module, the audience it addresses and the organization of the various chapters. It also includes the list of related documents to be referred, if any, and the conventions used in the document |
| Chapter 2 | <i>Bank Parameters</i> explains the maintenance of various basic details about your bank |
| Chapter 3 | <i>Ramadan Maintenance</i> explains maintenance of <i>Ramadan</i> year. |
| Chapter 4 | <i>Dealer Maintenance</i> explains how you can capture profiles of dealers involved in buying and selling of foreign exchange |
| Chapter 5 | <i>Branch Parameters</i> explains the process of creating and maintaining branches of your bank, with all necessary details |

| | |
|-------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Chapter 6 | <i>Account Branch Transfer</i> explains how you can maintain and process account transfers from one branch of the bank to another. |
| Chapter 7 | <i>System Dates Maintenance</i> explains how you can maintain system dates for the branches of your bank |
| Chapter 8 | <i>Web Service Maintenance</i> explains the process of WebService Mapping and other details regarding maintenance of external WebService. |
| Chapter 9 | <i>Accounts for Inter-Branch Transactions</i> explains how you can maintain internal accounts for branches involved in inter-branch transactions |
| Chapter 10 | <i>Currency Maintenance</i> explains the process of maintaining currencies in the system, with all necessary static attributes |
| Chapter 11 | <i>Maintaining Currency Denomination</i> explains the maintenance of standard currency denominations for each currency |
| Chapter 12 | <i>Expressing Amounts in Words</i> describes the details of maintaining amounts in words |
| Chapter 13 | <i>Defining Currency Pairs</i> explains the maintenance of static attributes for currency pairs for which exchange rate quotes are available |
| Chapter 14 | <i>Maintaining Exchange Rates</i> explains the maintenance of exchange rates used to buy and sell currencies one for another |
| Chapter 15 | <i>Maintaining Currency Spread for a Customer</i> explains the maintenance of currency spread and margin details for a customer |
| Chapter 16 | <i>Period Code Maintenance</i> explains the maintenance of financial periods into which each financial cycle is to be divided |
| Chapter 17 | <i>Status Code Maintenance</i> explains the maintenance of codes that you can assign to the different statuses that a contract or a customer account can attain |
| Chapter 18 | <i>Transaction Code Maintenance</i> explains the maintenance of codes that you can use to represent different types of transactions |
| Chapter 19 | <i>Account Revaluation Maintenance</i> explains the maintenance of parameters for account revaluation |
| Chapter 20 | <i>Maintaining Branch Holidays</i> explains the maintenance of the holiday calendar for the different branches of your bank |
| Chapter 21 | <i>Maintaining Currency Holidays</i> explains the maintenance of the holiday calendar for the different currencies in which your bank transacts |
| Chapter 22 | <i>Maintaining Clearing Holidays</i> explains the maintenance of the holiday calendar for the different clearinghouses with which your bank transacts |
| Chapter 23 | <i>Document Maintenance</i> explains about the type of documents to be submitted before opening an account and the document checklist to be maintained. |
| Chapter 24 | <i>Configuring Overrides</i> details on configuring overrides of the system. |





| | |
|-------------------|---------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Chapter 25 | <i>Maintaining Features</i> explains the method of installing features in a branch to improve the performance of the system during online or batch processes. |
| Chapter 26 | <i>Purging Data</i> explains the details of purging data. |
| Chapter 27 | <i>Support 24x7</i> explains about the 24x7 support features in FCUBS. |
| Chapter 28 | <i>Tanking of Maintenance Records</i> explains the process of tanking maintenance records. |
| Chapter 29 | <i>External Deal Maintenance</i> explains the process of capturing deals booked in an external system. |
| Chapter 30 | <i>Annexure B – File Formats</i> contains a list of file formats. |
| Chapter 31 | <i>Anti-Money Laundering Reporting</i> explains the process of guarding against money laundering, a facility provided by Oracle FLEXCUBE |
| Chapter 32 | <i>Developer and Developer Project Maintenance</i> explains how you can maintain details of the real-estate developer and developer projects. |
| Chapter 33 | <i>Project Financing</i> explains the process of maintaining the project finance transaction in a bank using the Project Detail and Maintenance screen. |
| Chapter 34 | <i>Error and Error Codes for Project Financing</i> lists all the error messages that you can encounter while working with this module. |
| Chapter 35 | <i>Reports</i> explains the procedure of generating Reports. |
| Chapter 36 | <i>Function ID Glossary</i> has alphabetical listing of Function/Screen ID's used in the module with page references for quick navigation. |

1.5 Related Documents

- The Procedures User Manual
- The Settlements User Manual

1.6 Glossary of Icons

This User Manual may refer to all or some of the following icons:

| Icons | Function |
|-------------------------------------------------------------------------------------|-----------------|
|  | Exit |
|  | Add row |
|  | Delete row |
|  | Option List |

2. Bank Parameters

2.1 Defining Bank Level Parameters

In the 'Bank Wide Parameters' screen, you maintain basic information about your bank such as its name, head office, account number structure, local currency and so on.

The details that you maintain in this screen will be made applicable to all branches of your bank. For instance, the account number structure that you define in this screen will be a common format for customer accounts in all branches of your bank.

Invoke the 'Bank Parameters' screen by typing 'STDBNKPM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Bank Parameters Maintenance' window. It includes a search bar 'Enter Query' and input fields for 'Bank Code *' and 'Bank Name'. Below this is the 'Head Office Branch' section with 'Branch Code *' and 'Branch Description'. A tabbed menu at the top of the main area includes 'Financial Preferences', 'General Preferences', and 'FATCA'. The 'Financial Preferences' tab is selected, showing 'Bank Default Currency Codes' with four rows for 'Local Currency *', 'Discount Currency *', 'Head Office Currency *', and 'Reporting Currency *', each with a 'Currency Description' field. There are also sections for 'Control Accounts For Real Entries' and 'Control Accounts For Contingent Entries', each with 'Currency Mismatch Control Account' and 'Value Date Mismatch Control Account' fields. Checkboxes for 'Auto Generate Currency Mismatch Entries' and 'Auto Generate Value Date Mismatch Entries' are located on the right. The bottom of the window contains a status bar with fields for 'Maker', 'Checker', 'Mod No', 'Date Time:', 'Record Status', and 'Authorization Status', and an 'Exit' button.

You can maintain the following details in this screen:

Bank Code

In Oracle FLEXCUBE a bank is identified by a unique four-character code. You can follow your own convention in devising this code. In all inter-bank transactions this code identifies your bank.

Name

You can also specify the detailed name of the bank. This name will always be displayed whenever the bank code is used.

2.1.0.1 Specifying Details of Head Office Branch

After specifying a code to identify your bank, you should specify details of the head office of your bank.

Code

From the list of the branches you have already maintained of your bank, designate one as your Head Office

Description

The description of the branch designated as Head Office is displayed.

2.1.1 Maintaining Financial Preferences

In this screen, you can maintain information regarding default currency for the branch, specify if balancing entries must be automatically generated in case of mismatches, define routing mask, clearing bank code etc.

2.1.1.1 Specifying Default Currency Codes

You can indicate currency preferences for your bank. You can specify preferences to indicate the default currencies for the following purposes:

- **Local** — The currency that you indicate as the local currency will be taken as the local currency for all branches of your bank and the default currency for all transactions input into Oracle FLEXCUBE. The income and expense balances of your bank will also be maintained in this currency
- **Discount** — If the discount rate for a particular currency is not maintained the discount rate of the specified discount currency will be picked up for discounting profits on forward foreign exchange contracts
- **Head Office** — The default currency for the Head Office
- **Reporting** — The default currency in which all financial reporting should be done

You will not have an option to modify the default currencies that you specify after the Bank Parameters record has been stored and authorized.

Auto Generate Currency and Value Date Mismatch Entries

You can specify that balancing entries must be generated automatically by Oracle FLEXCUBE, in the case of currency or value date mismatches in accounting entries due to transactions that are not balanced with respect to currency or value dates, for each branch (single entity) of your bank.

To specify the automatic generation of such balancing entries for currency mismatches, select the options 'Auto Generate Currency Mismatch Entries' and for generation of balancing entries to correct value date mismatches, select 'Auto Generate Value Date Mismatch Entries' in the Bank Wide Parameters screen.

If indicated in the Bank Wide Parameters, balancing entries will be automatically generated for any event if a mismatch of currency or value date entries (or both) is involved in any module of Oracle FLEXCUBE, with the exception of manually entered journal entries.

2.1.1.2 Specifying Control Accounts for Auto Balancing Entries (Real and Contingent)

If you specify that such automatic balancing entries must be generated, you can also specify the control accounts into which the entries must be booked.

There are two sets of accounts that you can maintain in the Bank-Wide Parameters screen, one for mismatches arising out of entries to real accounts and another for mismatches arising out of entries to contingent accounts. The relevant Control accounts must therefore be of Real or Contingent nature (as defined in the GL – Chart of Accounts). Such balancing entries will be automatically generated if a mismatch of currency or value date entries (or both) is involved in any module of Oracle FLEXCUBE, except Journal Entry.

In your Chart of Accounts, you must ensure that the following conditions are not indicated for the control accounts that you have specified for the currency mismatch and value date mismatch entries:

- Position accounting: Even if position accounting is set to “Yes” for the control account, the system will not pass any position accounting entries, since position accounting is done only for the main set of entries and not for the auto-balancing entries.
- Account revaluation: Account revaluation must be set for the control accounts since the effect of revaluing these balances would be offset the effect of revaluing the original GLs. (the GLs into which the main entries were posted).
- Direct posting: If you post a manual entry to one of the Control Accounts and the Position Entry Flag for the Control Account is set to “Yes”, then the system will do position accounting for that entry. Hence, for the GLs set-up as Control Accounts, the “Direct Posting” flag in the Chart of Accounts maintenance must be turned OFF.

Note

Additionally, it is also recommended that these Control Account GL's that you have specified in the Bank Wide Parameters screen for the mismatch entries are not used as part of Role to Head Mapping in any of the products. If maintained, the system would pass mismatch adjustment entries into the same GLs in which the main entries have been passed. There is no system-enforced validation of this and this aspect needs to be taken care of during Product set-up.

2.1.2 Generating Automatic Balancing Entries

In the case of transactions entered in any of the front-end modules of Oracle FLEXCUBE, the accounting process checks the entries at each business event, and automatically generates the balancing entries in case of a mismatch in currency or value date entries (or both).

Manually entered journal entries

In the case of manually entered journal entries, a journal batch that has been opened must be closed before it is authorized. During closure, the accounting process checks to see that the batch is balanced with respect to currency and value date entries. If a mismatch is detected, the accounting process raises an override to this effect. Depending upon how the override is configured, for your bank, the user who has opened the batch could adopt either of the following courses of action:

- If the override is configured to be an error, the system will not allow the user to close the batch without balancing the mismatches.
- If the override is configured to be a warning (either ‘Override’ or ‘Ignore’), the user can save the batch with the mismatches. No balancing entries are automatically generated by the system for the mismatch.

Uploaded journal entries

In the case of uploaded journal entries, a journal batch that has mismatched entries is not rejected, but an override is raised by the accounting process. Depending upon how the override is configured, for your bank, the accounting process takes either of the following paths:

- If the override is configured to be an error, then the batch is rejected, and must be uploaded again with the corrected entries.
- If the override is configured to be a warning, the accounting process automatically generates the balancing entries for the currency or value date mismatches, for the batch, and posts them to the requisite control accounts specified in the Bank Parameters.

In each case, the transaction reference for the balancing entries is the same as that of the original accounting entry, in which the mismatch occurred, and the other details of the balancing entries are, by default, the corresponding values in the original entries.

The mismatch balancing entries are generated in the following order or preference:

- Currency mismatch balancing entries
- Value Date mismatch balancing entries

In the case of mismatches in accounting entries due to inter-branch transactions, the inter-branch balancing entries are generated before any balancing entries for currency mismatches, and then, finally, the value date mismatches.

Routing Mask

A mask defines the manner in which a Routing Number is generated for your bank. It is on the basis of the routing number that Oracle FLEXCUBE processes clearing transactions.

The following is a typical mask format: 'BBBbbbSSS', wherein, 'BBB' indicates the bank code, 'bbb' indicates the branch, and 'SSS' indicates the sector to which the branch belongs. On the basis of the routing number, clearing transactions are routed to the appropriate branch of your bank.

Clearing Bank Code

Specify the code by which your bank is identified in the Clearing Network you participate in. This has to be the same as that specified for your bank in the Clearing Bank Code Maintenance screen.

2.1.3 Maintaining General Preferences

In this screen, you can define format masks (for general ledger, CIF), choose if batch numbers should be auto-generated by the system, specify the details for cheque numbering etc.

The screenshot shows the 'Bank Parameters Maintenance' window with the 'General Preferences' tab selected. The interface is divided into several sections for configuring bank parameters:

- Bank Information:** Bank Code, Bank Name, Head Office Branch, Branch Code, Branch Description.
- Financial Preferences:** General Preferences (selected), FATCA.
- Format Mask:** Cif Mask, General Ledger Mask.
- Spread:** Spread Application (dropdown), Spoof Files Purge Days, Inter Pay Lead Days.
- Cheque Numbering Details:** Scheme (dropdown), Cheque Number Mask.
- TRS Details:** Sort Code, Account Number.
- Trade License Details:** Expire Advice Generation Days.
- Mandatory Limit Tracking For Customer Type:** Corporate, Bank, Individual (checkboxes).
- Passbook Details:** Minimum Number of Digits for Passbook.
- Relationship Manager:** RM set up (checkbox).
- Year End Profit and Loss:** General Ledger, Transaction Code.
- General Ledger:** General Ledger Purge Days, Auto Batch, User Batch Restriction, SSO Enabled (checkboxes).
- Cheque Discounting Details:** Cheque Return Count for Drawer Blacklisting.
- Checksum Algorithm:** (dropdown), Cheques Number Unique for Branch, Lodgement Numbers Unique For Branch (checkboxes).
- Suspense Account:** Payment And Collection, Product Category.

The bottom status bar includes fields for Maker, Checker, Mod No, Date Time, Record Status, and Authorization Status, along with an Exit button.

2.1.3.1 Defining Format Masks

A format mask is a structure that you can define for various elements that need to be entered in Oracle FLEXCUBE. You can define format masks for the following elements:

- General Ledgers
- Customer Identification File codes
- Customer account numbers

Once defined, you can modify the structure of a format mask only if no Customer or General Ledger Account has been opened using the mask. Customer Account mask is defined from the 'Account Mask' Button.

For more details on defining customer account mask, refer the section titled 'Specifying Account Generation Parameters at Bank Level'.

CIF Mask

You can maintain a mask for generation of identification numbers (CIF Number) for customers of your bank. During customer information maintenance, the system will automatically generate the CIF numbers based on the mask you define here and the customer number range maintained at the branch level.

A CIF mask consists of a maximum of 9 digits. The CIF mask could have only numbers or could be alpha numeric or could also have the branch code as a part of it.

For instance, you can maintain the CIF Mask as 'bbbnnnnnn' where 'bbb' represents a three-digit branch code and 'nnnnnn' represents a 6-digit number.

GL Mask

You can indicate a mask for the general ledgers that are maintained for your bank. The mask that you define here will be enforced whenever a General Ledger is created in the Chart of Accounts screen.

A GL mask can consist of a maximum of nine alphanumeric characters. It can be built using a combination of numbers and letters to indicate for instance, the category of the GL - asset, liability etc., the GLs hierarchical position and so on.

Each element used to define the mask would represent a single character. To represent an alphabet of the English language, indicate "a". To represent a number, indicate "n". The last character would be a D or d, which indicates a check digit generated by the system. For a numeric check digit define it as 'd'; for an alphanumeric check digit define it as 'D'.

You may use any of the following punctuation in the GL mask:

- dash (-)
- comma (,)
- asterisk (*)
- Full Stop (.)
- Forward slash (/)

For example, You wish to create a two level GL structure for your bank. You could define the first two characters of the GL to represent the category asset, liability etc., aa; the next two characters, nn, to represent the first level GL; and the next three characters, nnn, to represent the second level GL. A GL based on the given structure would read as AS01001 where AS represents the GL category - asset; 01 represents the first level GL; 001 represents the second level GL.

For creating this structure you would define your GL mask as - aannnnn'd/D'.

If you want to define your second level GL with a 4 digit numeric code instead of 3; other parameters remaining the same your mask would read as aannnnnn 'd' 'D'.

2.1.3.2 Indicating Year-end Profit & Loss

General Ledger

At the end of any financial year the balances in the income and expense accounts are posted by Oracle FLEXCUBE into a separate year-end account for the purpose of consolidation of balances and turnovers. This account is called the Year End profit and loss General Ledger Account.

You also specify year-end profit and loss GL for each GL account you maintain in the 'Chart of Accounts' screen. The year-end account specified at the bank level is the default year end profit and loss GL for all GL accounts maintained in the 'Chart of Accounts - GL' screen. If you do not specify the account to which year end balances of a particular GL should be posted, it will be posted to the bank's year-end profit and loss account.

You can select a GL code from the option list of all assets, liabilities, income and expense GLs maintained in the chart of accounts screen.

Transaction Code

Indicate the transaction code that should be used to post the balances in the income and expense accounts to the year-end GL account.

You can select a transaction code from the list of transaction codes maintained in the 'Transaction Code Maintenance' screen.

Spread

Capture the following details.

Spread Application

Indicate the transaction legs for which the spread should be applicable. Choose the appropriate option from the following available in the adjoining drop-down list:

- Single Leg
- Both Legs

Spool File Purge Days

Specify the duration for which spool files should be stored in the spool file directory.

Interpay Lead Days

Specify the inter-pay lead days required for fetching billing records for inter-pay files for automatic billing of clients..

Auto Batch

Each time you post journal and multi offset entries, you need to open a batch. You can specify that the batch numbers of the journal entry batches opened in your bank should be generated automatically by enabling the Auto Batch option.

Consequently, the system automatically generates batch numbers while posting journal and multi offset entries.

2.1.4 Placing User Restrictions on Data Entry Batches

You can restrict the usage of batches to specific user by placing bank-wide User level batch restrictions. If you enable this option as a Bank Parameter, you need to allocate the batch number range for each user through the 'Batch Restriction Maintenance' screen.

The restriction on the usage of batch numbers is made applicable on data entry and PC transactions. The user will be allowed to enter only those batches reserved for the user profile. As a result, each time a user specifies a batch number; it will be validated against the 'Allocated Batch Number Range'.

This feature is applicable only when batch generation is manual. Therefore, if you enable this option, you must ensure that the Auto Generate option has not been enabled. In a scenario where the User Restriction for Batch Number field is enabled and Auto Batch option has also been enabled, the system displays an error message as "Not a Valid Batch Number For the User".

In case you choose to auto generate batch numbers, the System will not perform the batch restriction validation.

You can invoke the 'Batch Restrictions Maintenance' screen by typing 'STDBRRES' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Batch Restriction Maintenance

New Enter Query

UserID *
User Name
Branch Code *
Branch Name
Module Code *
Module Description

Allocated Batch Number Range

1 Of 1 Go

| Start Number * | End Number |
|----------------|------------|
|----------------|------------|

Fields

Maker
Checker
Mod No
Date Time:
Date Time:
Record Status
Authorization Status

Exit

Specify the following details in this screen:

- The User Profile for which the restrictions are being maintained. A list of all the User Profiles with access rights to the DE and PC modules is displayed in the option list. You can select the appropriate.
- The branch of your bank for which the restrictions will be made applicable. You can either choose a specific branch or make the restriction applicable to 'All' the branches of your bank.
- The module for which you are maintaining the Allocated Batch Number Range. This can either be PC or DE.

- The batch number range, which is indicated in terms of Start and End numbers. The range that you specify is allocated to the user. For distinct numbers, the start number and end number of the range will be the same.

Note

While processing DE and PC transactions, the batch number specified by the user is validated against the allotted range. If the validation fails, an error message is displayed.

These validations are made applicable even during the Batch Upload operations for the following functions:

1. Journal Online – Single Entry
2. Multi-offset Entry
3. Teller Transaction Input

SSO Enabled

To enable Single Sign On (SSO) for your installation check the SSO Enabled check box. This enables restricted login from external systems into Oracle FLEXCUBE.

General Ledger Purge Days

You can specify here the maximum number of working days, the average GL balance computation for which is to be retained in the System.

2.1.4.1 Specifying Cheque Numbering Details

Scheme

In Oracle FLEXCUBE, cheque numbers can be generated automatically or can be manually entered. If you indicate manually, you can draw up numbering conventions and assign numbers to the cheques that are issued.

Cheque Number Mask

Specify the mask of a cheque number to be used by the bank. You can define numeric cheque mask as a series of N.

While defining an alpha numeric cheque mask, the alphanumeric character should always precede the numeric characters. For example: AANNNN, A being alpha numeric character and N being numeric character. Numeric characters should always follow the alpha numeric characters.


If cheque numbering scheme is 'Automatic' and checksum algorithm is selected, the 'Cheque mask' can be defined as only numeric. The cheque mask can contain only 'N' or can start with a 'T' followed by 'N'. If the cheque mask contains a 'T' in the first position, it indicates that the cheque is of type EURO or COMMERCIAL. If the mask contains only 'N', then the cheque is only numeric and cannot be EURO / COMMERCIAL. An appropriate error message is displayed if cheque numbering scheme is 'Automatic' and cheque number mask defined contains anything other than 'N' or 'T' in the first position.

If the cheque numbering scheme is 'Automatic' and checksum algorithm is selected at bank parameter, the cheque mask cannot be defined as alpha-numeric. The system validates if the cheque mask is alphanumeric and inventory is enabled at bank parameter. The system displays an appropriate error message as 'Alpha-numeric Cheque number is not supported as Inventory tracking is enabled'.

Checksum Algorithm

If you choose the automatic generation option you can indicate the algorithm based on which the cheque digit should be generated. A cheque number consists of three components:

- A check digit
- A cheque type
- A running serial number



You have the option to choose the algorithm to be used to arrive at the check digit. Currently Oracle FLEXCUBE supports only the Modulo-7 algorithm. Based on this algorithm the check type and serial number is divided by seven, and the remainder is taken to be the check digit. If the remainder is zero, then the check digit is set to seven.

The cheque type indicates whether the cheque is a Euro or Commercial cheque. The numeral 1 before a cheque serial indicates a Euro cheque and 2 indicates a Commercial cheque.

The cheque serial number is generated sequentially starting from 0001. This running serial number is assigned taking into account the last check number issued for the account.

Cheque Numbers Unique For Branch

For cheque numbers that are automatically generated, you can choose to make cheque numbers unique across the branches of your bank.

If you indicate that serial numbers need not be unique, you can have the same cheque number assigned to cheque leaves of different accounts within a branch. In effect cheque numbers remain unique to an account.

Lodgment Numbers Unique for Branch

You can indicate whether lodgment leaves must have unique numbers in a branch, or must be unique for individual accounts.

For example, in the Bank Wide Parameters, you have specified that lodgment book numbers must be unique for the branch. This means that lodgment numbers need to be unique across all accounts of that branch. For instance, if a book is maintained with the Start Number as 1, and containing 25 leaves, you cannot start another book in respect of any other account, with these numbers.

If you have specified that lodgment book numbers must be unique to accounts in the branch, and a book is maintained with the Start Number as 1, and containing 25 leaves, you cannot start another book in respect of the same account, with these numbers. However, you can start a book with the same numbers in respect of another account in the branch.

2.1.4.2 Specifying TRS Details

You can maintain the following details that will be used by the system to raise direct debit for Tax Relief at Source (TRS) rebate availed by customers on mortgage loans. The direct debit is raised during the End of Day (EOD) process after the LD batch processes.

Sort Code

Specify the destination bank code for which the bank raises direct debits for TRS claims.

Account Number

The destination account for which the bank raises direct debits for TRS claims.

Payment & Collection Product Category

Specify the Payments and Collections (PC) product category that would be used by the bank to raise direct debits for TRS claims.

Suspense Account

Specify the account that would be debited with the TRS amount, to credit customer account.

For more details about processing for TRS, refer the Loans module user manual and the Payments and Collections user manual.

2.1.4.3 Viewing Trade License Details

Expiry Advice Generation Days

If the trade license is set to expire on a particular date, the number displayed here denotes the number of days before that date when an advice is generated and sent to the customer informing about the impending expiration.

2.1.4.4 Specifying Mandatory Limit Tracking For Customer Type

You can maintain limit tracking as a mandatory option based on the customer type.

Corporate

Check this box if it is mandatory to link customer of Corporate type to credit line.

Bank

Check this box if it is mandatory to link customer of Bank type to credit line.

Individual

Check this box if it is mandatory to link customer of Individual type to credit line.

If a contract is saved without selecting the limit line for customers checked for mandatory limit tracking, then the system displays the error message as "Limit tracking is mandatory for this customer <Customer CIF>".

Note

- By default the customer type is selected as 'Individual'. However you can modify it.
 - At the customer maintenance level, system defaults 'Track Limits' option based on the option set here.
-

2.1.4.5 Specifying Cheque Discounting Details

Cheque Return Count for Drawer Blacklisting

The system displays the number of cheque returns for a drawer. During the cheque return processing, the system check the number of cheque returns against this maintenance and marks the drawer as 'Blacklisted' drawer.

2.1.4.6 Specifying Passbook Details

Minimum Number of Digits for Passbook

Specify the minimum number of digits for creating passbook number. The system defaults the minimum value 10. However you can modify it.

2.1.5 Specifying UDF Details

You can associate values to all the User Defined fields created and attached to the Bank Parameters Screen. You can view the list of User Defined fields associated by clicking the 'Fields' button. The screen appears as shown below:

| Field Name * | Value | Value Description |
|--------------|-------|-------------------|
|--------------|-------|-------------------|

You can enter the value for the UDFs listed here in the 'Value' column.

For more details on how to create user Defined fields, refer chapter 'Creating custom fields in Oracle FLEXCUBE' in the User Defined Fields User Manual under Modularity.

2.1.6 Specifying Account Generation Parameters at Bank Level

Account numbers in your bank are generated in the format of the account mask that you specify through the 'Account Parameters' sub-screen of the Bank-wide Parameters screen. Click 'Account Mask' button in the Bank-wide Parameters screen. Account Parameters screen is displayed. The screen appears as shown below:

Customer Account Mask

Checksum Algorithm

User Defined Algorithm

Customer Account

Consumer Number

Start Account Number

End Account Number

☐ Customer Account Auto Generate

☐ Loan Account Auto Generate

Auto Account Creation

Start Account Number

End Account Number

Note

Since account level parameters are defined at the bank-level, by default these parameters will be defaulted to all the branches of your bank. However, individual branches of your bank will be allowed to change these specifications.

2.1.6.1 Specifying Customer Account Mask

Account numbers can either be generated automatically or you can choose to allocate them manually. In Oracle FLEXCUBE you have the option of maintaining three types of account masks.

They are as follows:

- **Alphanumeric** – this type of an account mask is a combination of alphabets and numbers where you can build the mask with components such as the Branch Code, the Account Class, the Currency Code, a check digit, etc
- **Numeric** - is a numeric type of account mask where the checksum algorithm associated with the account mask is either Modulo 11, Modulo 11 with weights or Modulo 97.
- **Pure Numeric** – is a numeric type of account mask, which does not have a checksum algorithm, associated with it. If you are maintaining a pure numeric mask you have to identify the start and end account number which is to be associated with it.

Alphanumeric customer account masks

The alphanumeric customer account mask can have a maximum of twenty alphanumeric characters. It can comprise of one or more of the following elements in combination:

- **Account Class** — Use “ACCLASS” to indicate that the account class to which the account belongs should be part of the mask.
- **CIF Number** — You can incorporate the nine-character CIF code assigned to the customer into the mask. To do so indicate ‘CIF Number’ in the mask.
- **Currency** — To add the currency of the customer account, use ‘CCY’
- **To indicate an alphabet or number** — Each element used to define the mask would represent a single character. To represent an alphabet of the English language, indicate “a”. To represent a number, indicate “n”.
- **Punctuation Marks** — When defining the customer account mask you have the option of separating the elements. To do this, you may use the following punctuation marks:
 - Dash (-)
 - Comma (,)
 - Asterisk (*)
 - Full stop (.)
 - Forward slash (/)

For Check Digit - The last character in the customer account mask should always be a ‘D’ or ‘d’. This indicates the check digit, which is generated by the system. When specified in the mask, the check digit component is generated using either of the following methods:

- Modulo 11
- Modulo 97
- Modulo 11 with Weights
- User Defined Algorithm

If you choose Modulo 97, all components of the account mask (for example, the Branch Code, the Account Class, the CIF ID, etc.) should be numeric. For example, if you enter ‘bbb’ in the

account mask field (indicating that the branch code should be part of the account number), and choose the Modulo 97 option, ensure that the branch code is a numeric value, such as '000', '123', etc.

Note

The maximum length of twenty characters for the customer account mask is inclusive of the check digit

All customer accounts that are entered in any branch of your bank will compulsorily have to conform to the mask.

For example, you want the following elements to be part of the customer account mask:

The currency of the account

The nature of the account (savings, current etc.) and

The Customer Id

Given the above criteria the customer account mask would be:

AClassCCyCIfNumbern'D'

This corresponds to:

LLLLL\$\$\$CCCCCCCnD

All customer accounts entered in any branch of your bank would now comprise of these elements, in the order defined in the mask.

A customer with CIF number 10005 has opened his first USD savings account with your bank, and the Account class for savings accounts is INDSB. His account number would read:

INDSB-USD-10005-1'D'

Similarly, the second GBP current account of a corporate customer with CIF Number 20005, would read

CUCOR-GBP-20005-2'D'

'CUCOR' being the account class representing current accounts of corporate customers.

Characters Supported for Various Fields in Account Mask:

| Field | Mask character | Max length supported |
|-------------------------------|----------------|----------------------|
| Account class code | L | 6 |
| Account code | T | 4 |
| Currency code | \$ | 3 |
| Currency type | Z | 3 |
| Customer number | C | 9 |
| Branch code | b | 3 |
| Serial Number | S | - |
| Numeric value(user to input) | n | - |
| Alphabet value(user to input) | a | - |
| UDF | U | - |

Note

You must specify the mask character in the same case as mentioned above.

| Field | Case 1 | Case 2 | Case3 | Case4 |
|---------------|-----------|-----------|-----------|-----------|
| CIF number | 015005624 | 015005624 | 015005624 | 015005624 |
| Currency code | GBP | GBP | GBP | YUV |
| Currency type | O | O | O | YA1 |
| Account class | SAVINV | CACIN | 123456 | SAVINV |
| Account code | SA12 | SA12 | 8909 | SA12 |
| Branch code | 014 | 015 | 015 | 015 |

| Mask maintained | Booked against | Chk sum Algorithm | Generated Account Number |
|-----------------------------|----------------|-------------------|---------------------------|
| LLLLLLL\$CCCC CCCCSSd | Case 1 | Modulo 11 | SAVINVG- BP15005624019 |
| LLLL\$\$\$TTCCCC CCCCSSd | Case 1 | Modulo 11 | SAVIGBP- SA15005624028 |

| Mask maintained | Booked against | Chk sum Algorithm | Generated Account Number |
|-----------------------------|----------------|-------------------|----------------------------------------------------------------------------------------------------------------------------------|
| LLLLLL\$\$\$ZCCC CCCnnd | Case 2 | Modulo 11 | CACINGB- PO005624997 |
| nnnnnnnD | Case 1 | Modulo 11 | 09888994 |
| bbb- bLLLZZZCCCCC nnd | Case 4 | Modulo 11 | 015SAVYA105624 074 |
| LLLLLL\$\$\$CCCC CCCSSDD | Case 1 / 2 | Modulo 97 | Error. Will not be able to generate the check digit. The control digits value must be numeric for Mod- ulo 97. |
| LLLLLT- TTTTCCCCSSD D | Case 3 | Modulo 97 | 123456890900562 40150 |

Customer Account Number Containing a UDF Value

While defining a customer account if you include 'U' in the account mask, it indicates that the customer account numbers will have the value of a user-defined field.

The number of U's will depend on the length of the UDF value that has to be included in the customer account number. For example, if you want to include 3 characters from a UDF, the account mask should consist of UUU (in addition to other parameters which you want to include in the customer account numbers).

Note

- A user-defined field can be part of the customer account mask only if the customer account number generation is not automatic.
 - Since a customer account number in Oracle FLEXCUBE can accommodate only up to 20 characters you have to ensure that the account mask you have defined does not exceed this number.
-

Numeric Account Masks with Modulo 11 and Modulo 97 as Checksum Algorithms

A numeric type of mask can have a maximum of twenty numeric characters, inclusive of the checksum algorithm.

If you associate Modulo 11, as the checksum algorithm, a single character D will be appended to the numeric mask. Let us assume that you have an account mask with five numeric values – 'nnnnn' and associated Modulo 11 as the checksum algorithm. The system automatically appends 'D' to the numeric mask. The generated account numbers will have the following format – nnnnnD.

If the Account mask is Alphanumeric, and check sum digit is needed as per Modulo 11, then the check digit- 'd' has to be manually specified in the mask. For example, if you need an account mask as 'bbbCCCCCSS', then considering Modulo 11 check sum digit, you need to input the mask as 'bbbCCCCCSSd'.

Similarly, if you associate Modulo 97, with an account mask of five numeric values, the system appends a double-digit value of DD to the mask. The generated accounts will have the following format – nnnnnDD

Note

As system automatically appends DD in case of Modulo 97, if you input the customer mask with 'DD', system will display the error message as 'Cannot have D denoting Alphanumeric Characters'.

if you input 'dd' in the mask, then system displays the error message as 'Cannot have d denoting Alphanumeric Characters in account mask while using mod97 Checksum algorithm'.

System automatically appends DD always at the end of the Mask.

| Algorithm | Contents of the mask | Check sum digit | Check digit character | Remarks |
|------------------------|----------------------|-----------------|-----------------------|-------------------------------------------------------------------------------------------------------------|
| Modulo 11 | Alphanu- meric | User to input | d | Check digit should be specified manually in the mask |
| Modulo 11 | Numeric | Auto append | D | System appends the check digit automatically, however, the mask characters should be 'n' for example, nnnnD |
| Modulo 97 | Alphanu- meric | Auto append | DD | If the values for the mask are alphanumeric, then check digit will not be generated |
| Modulo 97 | Numeric | Auto append | DD | - |
| wing format – nnnnnDD. | | | | |

Numeric Account Masks with 'Modulo 11 with Weights' as Checksum Algorithm

The account mask with 'Modulo 11 with Weights' algorithm can have a maximum of 13 digits. It comprises of the following elements:

- Branch Code (3 digits) – Indicates the branch at which the customer account is maintained.
- Account Code (1 digit) – This will indicate the account code of the account class to which the customer account belongs. During account number generation (in the Customer Account Maintenance screen), you need to select the account class from the option-list provided. The system will then convert it to the account code maintained for that account class. The account code thus becomes a part of the customer account number.
- Currency Type (1 digit) – This will represent the currency type of the account currency. As explained for account code, you will select a 3-digit currency code during account generation. The system will convert it to the currency type maintained for that currency. The currency type will then form a part of the account mask.
- CIF Number – You can also include the CIF number of the customer as part of the account mask. The CIF number is automatically generated by the system when you capture customer details in the Customer Information Maintenance screen. During customer account maintenance, you can select the CIF number from the option list provided.

Sequence Number (1 digit) – The sequence number is automatically generated by the system for a combination of account code + currency type + customer. This means that, for this combination, you can maintain nine accounts. To maintain the 10th account for the same combination, the system will use the 'Dummy Customer No. Range' maintained at the branch level'.

Refer the section titled 'Creating Branches' of this document for more details on dummy number range.

- Control Number (1 digit) - This is the 13th digit of the account number. This number is also automatically generated by the system based on the 'Modulo 11 with Weights' algorithm.

For the above combination, the customer account mask would be:

'bbbTZCCCCCSD'

Where,

- bbb – is the branch code
- T – indicates the account code
- Z – is the currency type
- CCCCCC – is the CIF number of the customer
- S – is the sequence number for a combination of account code, currency type and customer
- d – is the control number generated by 'Modulo 11 with Weights' algorithm

The following example illustrates the manner in which the system calculates the 13th digit for a customer account number using the 'Modulo 11 with Weights' algorithm.

Assume that the account number of a customer is '000-4-1-123456-1'. As per this algorithm, the value of each position (1 to 12) is multiplied with the weight for each position (the weights are provided by your bank). Further, the sum of the product obtained is divided by 11. The remainder of the division will determine the value of the 13th digit.

The position-wise weight and account number and the product (of weight and number) is as follows:

| | | | | | | | | | | | | |
|----------|---|---|---|---|---|---|---|---|---|----|----|----|
| Position | 1 | 2 | 3 | 4 | 5 | 6 | 7 | 8 | 9 | 10 | 11 | 12 |
|----------|---|---|---|---|---|---|---|---|---|----|----|----|

| | | | | | | | | | | | | |
|-----------------|---|---|---|---|----|----|----|----|----|---|---|---|
| Weight (W) | 2 | 4 | 8 | 5 | 10 | 9 | 7 | 3 | 6 | 2 | 3 | 5 |
| Acct. No (N) | 0 | 0 | 0 | 1 | 2 | 3 | 4 | 5 | 6 | 4 | 1 | 1 |
| Product (W * N) | 0 | 0 | 0 | 5 | 20 | 27 | 28 | 15 | 36 | 8 | 3 | 5 |

Sum of the product = 147.

Divide the value 147 by 11 to obtain the remainder

Remainder = $(147/11) = 4$

As per this algorithm, if the remainder is 10, then the control number will be zero. If it is any value other than 10, the remainder itself will be taken as the control number.

Therefore, the 13th digit = 4.

The customer account number will now read as '000-4-1-123456-1-4'

Numeric Account Masks with User Defined Algorithms as Checksum Algorithm

If the check digit component within a Customer Account Number is to be generated using a method of your choice you must identify the following:

- The User Defined Algorithm for the Customer Account Number – this identifies the name of the user-defined algorithm for check digit generation of account numbers.
- The User Defined Algorithm for Consumer Number – this stores the name of the user-defined algorithm for validating consumer numbers.

While capturing Customer Account numbers, the System checks for your specification for the checksum algorithm. If you have selected User Defined, the check digit is generated using the specified user-defined algorithm.

- Unused sequence numbers of CASA cannot be tracked for re-use if the sequence number is generated by user defined algorithm

Since these parameters are maintained for your bank, they are defaulted to the branches of your bank. You will not be allowed to change these for a specific branch of your bank.

Note

Unused sequence numbers of CASA can be tracked for re-use only if the customer account mask contains numeric mask.

- If the account mask contains any of the following characters, the lost account number is re-used only if the same customer opens another account with the same branch code, account class, currency & sequence number combination:
 - C(Customer number)
 - b(Branch)
 - T(Account class)
 - Z(Currency)
 - S(Single digit sequence number)
 - SS(Double digit sequence number)
- Unused customer account number is reused in the same day, except in the following scenarios:
 - Session termination for the current user

- Multiple windows opened for the same Function ID by the current user.

Pure Numeric Masks

A numeric account mask, which does not have a checksum algorithm associated with it, is called a pure numeric mask. Since it does not have a checksum algorithm associated with it you will have to specify the start and end account numbers and enable the auto-generated option.

The start account number forms the basis on which customer accounts numbers are to be generated. Similarly, you will not be allowed to maintain account numbers beyond the end account number.

Let us assume, that you have maintained the following details in the Account Parameters screen at your bank:

| Customer Account Mask | nnnnn |
|----------------------------|-------|
| Start Account Number | 1 |
| End Account Number | 50000 |
| Cust Account Auto Generate | Yes |

While generating a new account number the system will automatically generate 00001 corresponding to nnnnn. The next account will be – 00002.

Note

'n' is allowed in the account mask, only if auto account number generation is selected at branch level.

Including Value of a UDF as Part of Customer Account Number

If your bank has not opted for automatic generation of account numbers, you can specify a structure for customer account numbers. The structure can be a combination of CIF number, account class, value of a user defined field, currency, branch code, alphabets/numeric and a check digit which is automatically generated by the system.

For example, an account mask is CCCCCCLLbbbUUU\$\$\$ad.

This implies that a customer account number will contain:

CIF Id – represented by C

Account Class represented by L

Branch Code represented by b

Values of a user defined field represented by U

Any user-input alphabet represented by a (enter 'n' if you want to include a numeric)

Currency Code represented by \$\$\$

A check digit (which is automatically generated by the system) represented by 'd'

Note

The number of C's in the account mask should match with the CIF mask that you have specified. For instance, if the CIF mask is aaaannn (7characters), the account mask should consist 7 C's to include the CIF Id in the customer account number.

The value of a user-defined field can be used to include an additional parameter (for example: the code of the country to which the customer belongs) in the customer account number.

The steps involved for including the value of a user-defined field in a customer account number are as follows:

1. Include 'U' in the customer account mask to indicate that the customer account number should contain the value of a UDF
2. Create a new user defined field
3. Link it to the Function Id STDCIF
4. Specify the value of the user defined field at the time of creating a customer
5. Specify the UDF whose value has to be included in the customer account number to the Oracle FLEXCUBE implementer. The implementer will indicate this at the back end.

Maintaining Ten Digit Masks with Running Sequence Numbers

You can maintain a 10-digit mask of any combination, wherein the last two digits will necessarily be a running sequence number. This number will be automatically generated by the system. For instance, if you want to maintain a mask for the customer number and currency combination followed by the two digit running number, you will have to maintain the mask as CCCCC\$\$\$\$SS. Here, CCCCC stands for the customer number, \$\$\$ stands for the currency of the account and SS stands for the running number. The system will generate the last two-digit number in a continuous sequence irrespective of the combination that you specify in the mask.

For example, let us assume that you want the customer account number to be a combination of the customer number and the account currency followed by the serial number. To achieve this, you have to specify the mask as CCCCC\$\$\$\$SS. Based on this mask, for a customer with CIF ID 40207 with account in USD, the account number will be 40207USD01. If the same customer has another account in GBP, the next account number would be 40207GBP02. That is, there will not be any holes in the system generated running number.

2.1.6.2 Specifying Auto Account Creation Parameters

You may wish the system to automatically create current accounts for customers at the time of loan initiation. These system-created current accounts are for use as settlement accounts.

Here, you need to specify the range of numbers available for such auto created accounts by mentioning a start and an end number.

If you wish to retain the facility of auto creation of current accounts at loan initiation, you will have to ensure that the account number mask does not have any user input character.

2.1.7 Defining Bank-wide Preferences

In the Bank-Wide Preferences screen, you can specify the following:

- The route of inter-branch accounting — through HO, through RO or directly between branches
- Exchange rate preferences — to be maintained for the bank as a whole or at each branch

- Preference relating to update of GL balances — on-line or at the End of day
- Preference relating to Position Accounting
- Interface details

Click the 'Preferences' button to invoke the 'Preferences' screen.

Preferences

- Interface Details

Journal Account

Width

- Inter Branch Scheme

Inter Branch Entity

Inter Branch Account Schedule

- Fund Inter Branch Scheme

Inter Branch Account Schedule

Inter Branch Entity

- Preferences

☐ Online General Ledger Update

☐ Auto Generate CIF Numbers

☐ Re-Generate unused CIF ID

☐ Re-Generate unused CASA no

☐ Copy Exchange Rates to Branches

☐ Position Accounting Required

☐ Propagate Customer Address to Nodes

☐ Propagate CIF to other Nodes

☐ Propagate Bank Instruction Codes Details to Nodes

☐ Pair wise Positioning Required

☐ Branch wise Limits

☐ Limits History Required

☐ Daily MIS Refinancing

☐ Propagate Floating Rates to Branches

☐ Allow Inventory Tracking

Customer Id Mask Level

Mudarabah Fund Share Holder Balance Type

☐ Staff Account Restriction Required

☐ Auto Account Closure

Node wise CIF mask Maintenance

Ok Exit

Interface Details

Specify the following details:

Journal Account

Specify Journal Account of the Interface details

Width

Specify width of the interface.

Inter Branch Scheme

Indicate the following details.

Inter Branch Account Schedule

You can indicate the route through which accounting entries for inter-branch transactions should be settled. You can select one of the following routes from the option list that is available:

- Choose 'Through HO' to indicate that inter-branch transactions should be settled through the Head Office
- If you specify 'Through RO' the accounting entries would be routed through the regional office. If two branches involved in a transaction do not report to a common regional office, the accounting entry would be routed through the HO
- If you specify 'Direct', each branch would have a direct accounting relationship with every other branch

The receivable and payable accounts between the branches, referred to as 'due from' and 'due to' accounts, are maintained in the 'Inter-branch parameters' screen.

For example, suppose the University Savings Bank has the following set up for its head office and branches in Headington, Oxford:

Roosevelt Avenue Branch, is the HO with Branch Code 000

Foxlake Drive Branch (Branch Code 001)

Mountainwood Road branch (Branch Code 002)

You have indicated that inter-branch transactions should be routed through the Head Office. Ms. Tanya Agnihotri has an account in Branch 002. She makes a cash withdrawal from Branch 001. This being an inter-branch transaction, Branch 001 will have to recover the money from Branch 002.

In this example the following movement of funds is involved:

- At Branch 001, the cash account is credited for the transaction amount and due from Head Office account debited.
- At Branch 000, the due from Branch 002 is debited and the due to Branch 001 is credited.
- At Branch 002, the Customer Account is debited and the due to Head Office account credited

Inter Branch Entity

Oracle FLEXCUBE allows you to post accounting entries related to inter-branch transactions to either of the following:

- Customer Accounts
- General Ledgers
- Both

If you select Customer Accounts as an inter-branch entity, you can specify the currency and the actual customer accounts involved in an inter-branch transaction between two branches of your bank. If the inter-branch entity is specified as 'General Ledgers', you need to specify the internal accounts that would be involved in a transaction between two different branches of your bank. If you select 'Both' option, it indicates that inter branch accounting entries could be posted for both GL and Customer accounts.

Fund Inter Branch Scheme

Indicate the following details.

Inter Branch Account Schedule

You can indicate the route through which accounting entries for inter-branch fund transactions should be settled. You can select one of the following routes from the option list that is available:

- Choose 'Normal' to indicate the inter-branch routing defined for corporate transactions will be applicable to the inter-branch fund transactions as well.
- Choose 'Through HO' to indicate inter-branch transactions should be settled through the Head Office.
- If you specify 'Through RO' the accounting entries would be routed through the regional office. If two branches involved in a transaction do not report to a common regional office, the accounting entry would be routed through the HO.
- If you specify 'Through RO and HO', the accounting entries would be routed through the Regional Office of the first branch, then the Head Office. From the Head Office, the entries would be routed through the Regional Office of the second branch.
- If you specify 'Direct', each branch would have a direct accounting relationship with every other branch.

The receivable and payable accounts between the branches, referred to as **due from** and **due to accounts**, are maintained in the '**Inter-branch parameters**' screen.

Inter Branch entity

Oracle FLEXCUBE allows you to post accounting entries related to inter-branch fund transactions to a General Ledger that you have specified.

If you choose '**Normal**' as the inter-branch routing, and you have not selected the option 'Allow Corporate Access' in the Branch Parameters screen, the Inter Branch transfer options you have chosen will be used.

If you have selected the option 'Allow Corporate Access' in the Branch Parameters screen and the branch is a fund branch, the entity will be defaulted as General Ledger. The GL will be based on the maintenance you have carried out in the Fund Inter Branch Accounts Maintenance screen, for the fund id. The same is explained in the chapter **Accounts for Inter-branch transactions**.

Online GL Updates

The update of GL balances can take place either on-line or during End of Day. For an on-line update select this checkbox.

Re-generate unused CIF ID

Check this box to indicate that the unused CIF ID needs to be re-generated automatically.

Note

Unused sequence number's of CIF is tracked for re-use only in the following scenarios:

- If the user cancels without saving new customer maintenance.

- If the user deletes a new customer before authorizing it.
 - Unused customer account is regenerated on next day post cancelling or deleting.
-

Re-generate unused CASA no

Check this box to indicate that the unused CASA number needs to be re-generated automatically.

Note

Unused sequence number's of CASA is tracked for re-use only in the following scenarios:

- If the user cancels without saving a new CASA maintenance.
 - If the user deletes a new CASA before authorizing it.
 - The sequence numbers marked during delete operation is re-used in ascending order. The sequence numbers marked during cancel operation is reused only from next working day to prevent concurrency issues.
-

Auto- Generate CIF Numbers

This indicates whether or not the CIF should be generated automatically. Check this box to indicate the CIF number needs to be generated automatically.

Note

Unused sequence number's of CIF is tracked for re-use only if the CIF is generated automatically.

Copy Exchange Rates to Branches

Exchange rates are maintained for a currency pair and are used to calculate the equivalent of one currency against the other. These exchange rates can be maintained in each branch or at the Head office. You can indicate your preference.

If you check against the option 'Copy to Branches' the exchange rates maintained at the Head Office will be made applicable to all branches of the bank. Leave it unchecked to indicate that exchange rates should be maintained at each branch.

Position Accounting Required

You can retrieve the position of a foreign currency, any time, by opting for position accounting in your bank. When you opt for position accounting, you maintain a Position GL and a Position Equivalent GL for every foreign currency maintained in your bank. The Position GL reflects the current position of the currency.

If you opt for position accounting while defining Bank-Wide Parameters, you have to maintain Position GLs and Position Equivalent GLs for every foreign currency that your bank deals in. When maintaining GLs for your bank, you can opt to link the different currencies, associated with the GL to either of the following:

- The Position GLs that you have specified for the currency (Your specifications in the Currency Definition screen will default here)
- Position GLs of your choice

Daily MIS Refinancing

As part of setting up the bank level preferences you can indicate whether MIS refinancing processing is required on a daily basis for the particular branch of your bank.

If you indicate that MIS refinancing should be done on a daily basis, refinance processing will be done on a daily basis for the following modules:

- Loans and Deposits
- Money Market

Note

You can indicate the rate type that is to be used for individual LD, and MM transactions while processing the contract.

Propagate Floating Rates to Branches

You have to indicate whether the floating rates maintained at the head-office of your bank should be propagated across all the branches of your bank.

Check the box positioned next to this field to indicate that floating rates need to be propagated across branches. Consequently, each time you maintain a floating rate for a particular rate code and currency combination at your bank, a corresponding floating rate record will be created and sent to all the branches of your bank.

Limits History Required

You can indicate whether date-wise limits history needs to be maintained for the Bank. If you choose to enable this option, the limits history is maintained at the following levels:

- Liability level history for storing liability records
- Limit level history for storing Lines records
- Line level history for storing Line Utilization records

Conditions for collating Limits History data:

- There is no retrospective effect on limits history.
 - Back-valued contracts and account transactions do not result in any adjustment to the previous records in the history. Such transactions are inserted with the current EOD date. Similarly any future-dated contracts and account transactions are also inserted with the current EOD dates.
 - In cases where the main line is changed to a sub line, the utilization is transferred from the old main line to the new main line and the effect cascades to the ultimate parent line. But existing records are not changed or updated.
 - Existing data will not reflect the change in the liability number for a customer.
- Revaluation has no effect on the limits history data
- Limits history is not maintained country-wise

The data is archived during the EOD processing. The history data is not updated for holidays.

Note

If there is no change for a liability/limit/line, data is not archived for that day.

Note

This option can be enabled or disabled at any point of time. Limits history will be recorded with effect from the day the option is enabled. Disabling the option will however not automatically purge history data.

You have the option of querying Liability history and drilling down to Limits Line history and further drilling down to Contract-wise Utilization history. Clean risk data is displayed only as of the date of query and history for the same is not maintained.

Branch wise Limits

This option indicates whether or not the limits tracking must be done at the branch level. If this box is checked, you will be allowed to view/change only the lines created from that branch for a given liability.

To illustrate, if you open any credit line facility in branch BR1, then in the Limit Restriction screen, the only branch available will be BR1.

Checking this option will also allow you to View details of line utilization at the branch level in the Limits Query screen.

For a total utilization of a global customer maintained in HO, you would have to generate a report of the limit utilization for each instance.

Pairwise Positioning Required

You have to select this option to indicate whether pair wise positioning entries need to be stored/handed off or not. If selected, the system will store position creating pair entries separately for handoff to other external systems.

When processing accounting entries, the system will check whether you have opted for pair wise positioning. If you opt for this option, the system will check for the following conditions in all the accounting entries that are posted:

- The set of entries posted are balanced i.e. total LCY debit is equal to total LCY credit
- At least one pair of accounting entry is in FCY
- Both the currencies are not the same

If the above conditions hold true, the system will store the entries along with the following information:

- Dr. Account: indicates the debit leg's account GL
- Cr. Account: indicates credit leg's account GL
- Event Code: is the event of the transaction
- Dr CCY/Bought Currency
- Dr. Amount/Bought Amount
- Cr. CCY/Sold Currency
- Cr. Amount/Sold Amount
- Dr Booking Date/Cr Booking Date
- Dr Value Date/ Cr Value Date
- Dr Transaction Code/Cr Transaction Code
- Exchange Rate
- Hand Off Flag

Note

While passing pair wise position entries, the main component will be passed with TRF_AMT tag and the equivalent entry will be passed with the AMT_EQUIV tag.

In case of accruals/revaluation also, if position entries are created, the corresponding entries will be stored separately for hand off.

Note

Pair-wise Positioning Required will decide whether position creating pair entries need to be stored by the accounting processor separately for handing off to other system.

Propagate CIF to other Nodes

You need to indicate whether or not the CIF number maintained in HO has to be propagated to other branches present in different instances. Check this box to indicate the CIF number has to be propagated to other Nodes/instances.

Propagate Customer Addresses to Nodes

You need to indicate whether or not the customer addresses maintained in HO has to be propagated to other branches present in different instances. Check this box to indicate the Customer addresses has to be propagated to other Nodes/instances.

Propagate Bank Instruction Codes Details to Nodes

This indicates whether or not the BIC data maintained in HO has to be propagated to other branches present in different instances. Check this box to propagate BIC details.

Maintenance of Customer Identification Mask at Branch/Node level

This option gives you the flexibility to define different CIF masks at the Nodes/Bank level. If you select 'Bank' from the option list, then the CIF mask given at Bank level will be applied to all the branches under it.

Mudarabah Fund Shareholder Balance Type

Specify whether the system should consider the month-end balance or the monthly average balance of the GL to compute the shareholders' investment in the linked *Mudarabah* fund. Choose from the following options available in the drop-down list:

- Monthly Average Balance
- Month End Balance

The option specified here will be common to all the shareholder GLs identified under the *Mudarabah* fund and once *Mudarabah* fund shareholder balance type is input and authorized, it will not be allowed to modify later.

Staff Account Restriction Required

Check this option to apply staff account restriction at the bank level.

Auto Account Closure

Check this box to enable Account Auto Closure functionality.

If you select 'Node' from the option list, you will need to maintain CIF masks at the Node level in the 'Node-wise CIF Mask Maintenance' screen. This would ensure that the branches maintained in different nodes/instances have different CIF masks.

Click 'Nodewise CIF mask Maintenance' button to access this screen. The screen appears as shown below:

| Nodes | CIF Mask | Auto Generate CIF |
|-------|----------|-------------------|
|-------|----------|-------------------|

You can specify the following details here:

Nodes

This indicates the node/instance for which the CIF mask is required. Select a node from the option list provided.

Customer Identification File Mask

This indicates the CIF mask for the corresponding instance/node. Select a CIF mask from the option list provided.

Autogenerate Customer Identification File Number

This indicates whether or not the CIF should be generated automatically. Check this box to indicate the CIF number needs to be generated automatically.

Allow Inventory Tracking

You can use this check box to allow/disallow inventory management and tracking. To use inventory management module, check this box.

Note

If inventory tracking is allowed then 'Cheque Numbering Scheme' should be left blank/null.

For more details on Inventory Tracking, refer the Instruments Inventory Tracking User Manual.

2.1.8 Maintaining FATCA Preferences

In this screen, you can maintain the details regarding the banks' own FATCA classification. You mainly need to maintain the details in the following screen to identify:

- If FATCA is applicable to the bank
- The banks' own FATCA classification
- The banks' IRS issued EIN as well as its issue and expiry date

You can maintain these details by clicking the 'FATCA' tab. The screen appears as shown below:

FATCA Applicable

Check this box to indicate that the FATCA rules are applicable to the bank.

Banks FATCA Classification

FATCA Classification

Specify the bank's own FATCA classification. The adjoining option list displays the all the allowed classifications maintained for customer type bank using the 'Customer Type-Wise FATCA Parameters' screen.

Employer Identification No. (EIN)

Specify the employer identification number (EIN) issued to the bank by IRS.

Note

All the statuses do not require employer identification number (EIN).

Issue Date/Date of Agreement

Specify the date on which the employer identification number (EIN) was issued by IRS; or the date on which the bank entered into an agreement with IRS.

Expiry Date/Date of Revalidation

Some classification requires revalidation of employer identification number (EIN) periodically. Specify the date on which the EIN is to be revalidated.

GIIN

Specify the global Intermediary Identification number issued to the bank by the IRS.

Remarks

Provide any remarks, comments or observations regarding the Bank's FATCA Classification.

3. Ramadan Maintenance

3.1 Introduction

Zakat is a charge which is applied on the balance in an account if the balance is above a certain threshold amount. This charge is applicable only to savings accounts and Term Deposits (TD). It cannot be levied on current accounts.

The minimum threshold amount above which *Zakat* will be payable is decided every year before *Ramadan*. In addition, the percentage to be applied on the capital amount for calculation of *Zakat* is also decided.

This charge is levied on the savings accounts and TD accounts at *Ramadan*. For savings accounts, *Zakat* is computed on the balance as on the first day of *Ramadan* for all active accounts. The applicable amount is then deducted from the accounts.

In the case of TD accounts, *Zakat* is computed whenever there is a redemption of the principal. It is computed on the redeemed principal amount, provided the first day of *Ramadan* (for any one year of the TD tenor) falls between the profit start date of the deposit and the maturity date.

For computation and collection of *Zakat* you need to capture the first day of Ramadan every year.

3.2 Maintaining Ramadan Day

You can capture the first day of *Ramadan* for a given year in the 'Ramadan Day Maintenance' screen. This is a bank-level maintenance that needs to be done at your Head Office. To invoke the 'Ramadan Day Maintenance' screen, type 'CSDRAMDN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Year*

First Day of Ramadan

Input By
Date Time

Authorized By
Date Time

Modification
Number

Authorized

Open

Here you can specify the following details:

Year

Specify the year for which you are capturing the first day of *Ramadan*. Note that you cannot maintain multiple records for the same year.

First Day of Ramadan

Specify the date on which *Ramadan* starts in the specified year. Note that the date should be valid as per the *Ramadan* calendar.

Refer the chapters titled 'Defining the attributes specific to an Interest or Charge product' and 'Daily Processing of Interest and Charges' in the Interest and Charges User Manual for details on Zakat computation and application.

4. Dealer Maintenance

4.1 Defining Dealer

At the time of entering the details of a foreign exchange, money market, or securities deal, you will be required to enter details of the dealer who has struck the deal.

The dealers at your bank, who are associated with the buying and selling of foreign exchange, money or securities in the treasury, should each be assigned an identification number (ID number). The dealer list is maintained for the bank through the 'Dealer Maintenance' screen. Invoke this screen by typing 'STDDEALR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Dealer Details' window. At the top, there's a title bar with a diamond icon and the text 'Dealer Details'. Below it is a menu bar with 'New' and 'Enter Query'. The main content area has two input fields: 'Dealer Id *' and 'Dealer Name'. Below this is a 'Fields' section with a table of fields: 'Input By Date Time', 'Authorized By Date Time', 'Modification Number', 'Authorized' (checkbox), and 'Open' (checkbox).

The following parameters need to be maintained to define a dealer ID:

Dealer Id

Enter a unique code to identify the dealer. The identification code can have a maximum of six alphanumeric characters.

The dealer will be identified by this code for all transactions entered in Oracle FLEXCUBE. You can also retrieve dealer-wise information on the treasury deals entered into by your bank.

Dealer Name

You can also enter a detailed name of the dealer. The name of the dealer will be displayed whenever the dealer Id is used.

5. Branch Parameters

5.1 Creating Branches

In the 'Branch Parameters' screen you create the various branches of your bank, define their reporting hierarchy, and maintain parameters such as their names, their address of location, SWIFT, TELEX, and HOST addresses.


In this screen you can do the following:

- Create the Regional Offices and branches of your bank by assigning each a unique branch code
- Maintain the address of location of each of the branches and also their SWIFT, TELEX and HOST addresses
- Specify the Suspense GL for posting all those accounting entries for which no GL has been specified or the specified GL has been closed
- Define preferences, such as - the retention duration, a CIF number for walk-in customers and the GL for netting FX contracts
- Maintain customer number range for generation of CIF numbers for customers of your bank.

The HO creates the branches at the bank level. All subsequent modifications on the table are done from the respective branches.

5.1.1 System Features

Oracle FLEXCUBE supports a three level reporting structure.



At the top stands the Head Office followed by the Regional Offices. At the lowest level are the branches. There can be any number of branches, but the number of regional offices is restricted to six. The system validates to check that the number of parent branches is not more than six. If the number of parent branches is more than six, system will give an error and restrict the number to six.

The branches report to the RO; and the ROs in turn report to the HO. Within this three level structure you can also have a branch reporting independently to the Head office (as branch, BR7 in the diagram).

It is also possible to have a two level reporting structure with only the HO and the branches, where each individual branch reports directly to the HO.

5.1.2 Creating Reporting Structure

The order in which you create the HO, the ROs and the branches should follow the hierarchy. Hence, the first branch to be created should be the HO, followed by the ROs, and then the branches.


The Head Office of your bank is created during installation. You only have to create the Regional Offices and the various branches. During installation, the system automatically populates this screen with the branch code and name of your Head Office that you have specified to the implementer. The 'Parent branch' and the Regional Office fields' also default to this branch code.

To create an RO, invoke a new screen. Then, enter the code and name of the RO against 'Branch Code' and 'Name' respectively. You do not need to specify the 'Regional office' because the HO Code is the default for the field. (All ROs report to the HO).

Then create all the branches. If a branch reports to an RO, to specify that RO is the branch's 'Regional Office', select the code you want from the option list provided for this field.

But before designating, you should authorize all the RO records you have created; the system will not allow you to use any unauthorized record.

(Diagrammatic Representation)



5.1.3 Basic Parameters for Branch

In Oracle FLEXCUBE, the Head Office and the Regional Offices are defined as branches. You can maintain the details of the Head Office, regional offices and branches in the 'Branch

Parameters Maintenance' screen. Invoke this screen by typing 'STDBRANC' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can specify the following details here:

Branch Code

This is the code you assign to the office or branch. The code acts as an identifier in the system for the office / branch. Input a code using a maximum of 3 characters, alphanumeric.

Branch Name

This is the name of the office or branch, the code of which is input. Enter the name using a max. Of 35 characters, alphanumeric

Branch Available

The system displays the Branch Available status. If the status is 'Yes', it indicates that the branch can accept transactions for the day and if the status is 'No' , then it indicates that the transactions will be accepted but it will be in effect only from the next business day.

Accordingly accounting entries will be passed checking the following, for tanking branch transactions:

- The Branch Available Status
- The Branch date and host date i.e. entries will be tanked if branch date is ahead of host date

When the Branch Available status is 'NO' or if branch date is ahead of host date, then the transactions will be tanked. These transactions will be untanked by the BOD program which runs post date change i.e. POSTDTCH.

Note

If you want to check whether the transaction is tanked or not, you should login to host and refer to the corresponding query function.

For more information on 'Querying the Transactions' refer Retail Teller, Clearing and Utility Payment Chapters under Oracle FLEXCUBE host module.

5.1.4 Maintaining General Details for Branch

You can maintain the branch details regarding the local currency, the parent branch, regional office of the branch, address details including telex, BIC etc.

Local Currency

Specify the currency of operation for your branch and the default currency for all transactions of your branch. The income and expense balances of your branch will also be maintained in this currency.

Parent Branch

Parent Branch is to define an alternate reporting line, other than the three level HO-RO-Branch structure. The 'Parent' for all the branches you create is the HO code (default). To specify the Parent, other than the HO, select from the options displayed. The name of the parent branch is displayed alongside.

Regional Office

This is the branch code of the Head Office or Regional Office to which the branch (whose code is input eg. Branch Code) reports.

For a Head Office or a Regional office, this code should be the Head Office branch code, which is also the default for this field. For the branches, specify that branch as the RO, to which the branch reports. Select from the list of options displayed.

Country Code

Specify the code of the country in which the branch operates. Select from the options provided in the pick list

Customer Identity

Specify the customer's identity. During maintenance of payments & collections periodic instructions, system defaults the customer number here.

GL Class

Specify the GL Class. The adjoining option list displays a list of all the valid GL class codes and their description. You can choose the appropriate one.

Note

You can also select 'ALL' as an option. This indicates that all the GL codes are allowed for this branch.

5.1.4.1 Specifying ATM Details

Specify the following details

ATM Branch

Specify the ATM branch.

Institution Identification

Your bank may have a branch or multiple branches for different countries. You have to capture the identification code that uniquely identifies your bank branch in the ATM transactions interchange environment. Specify a code to identify the institution. This institution ID will help identify whether a particular transaction has been sent from an external network or whether it has originated from your bank branch.

Inter Branch Transaction Code

You can specify the Transaction Code through which accounting entries for inter-branch transactions should be settled.

Customer Transfer

Check this option to indicate that transfer transaction should be permitted through the ATM

5.1.4.2 Specifying Address Details

For each branch of your bank you maintain the following parameters:

Branch Address

Input the address of location of the branch. Each line can have a maximum of 35 characters.

BIC

Input the SWIFT address for a branch using 8 or 11 characters, alphanumeric

Telex

Specify the branch's TELEX address, using a maximum of 14 characters, alphanumeric

Host Name

Against 'HOST' enter the name of the Host server for this branch, in not more than 35 characters, alphanumeric

Time Level

In this field is displayed the system time level status, represented by a number between 0 and 9

In Oracle FLEXCUBE, user access to the system can be controlled by assigning each user and the system, a time level. Both the system and the users are set to different time levels. Only those users who have a time level equal to or greater than the system time level can log into the system.

A control clerk, during the EOC process, does the change in time level status

Fund Branch

Even though the fund and the bank are in the same database, the fund is treated as a different legal entity and as such the books of the fund are maintained separately from those of the bank. Funds are created in a separate branch and any transaction initiated in the fund branch belongs to a fund. Check this box to indicate that the branch you are maintaining is a fund branch. Since the fund is a different legal entity, it should not be possible to initiate inter-branch accounting entries from the fund branch.

Any settlement with an external entity is routed through the normal settlements interface. In order to facilitate this, all the account fields in the system accept only the accounts in the transaction branch, if the branch happens to be a fund branch.

Allow Corporate Access

Select this option to specify that the fund subscription/redemption operations in the fund branch can access the accounts of corporate branch.

Note

- You will not be allowed to change this field once the branch record has been authorized.
 - This field will be enabled only if the branch is a fund branch.
-

External Value

Specify the name of the branch as maintained in an external system. This value can be used to interface with the external system.

EOC Status

Under EOC status one of the following alphabets will be displayed which stand for the following:

B - Beginning of financial input; indicates system transactions in progress

I -- Indicates that user transactions are in progress

T-- End of user transaction input; indicates system transactions in progress

F -- End of financial input; system transactions also completed

E -- End of Day, Branch awaiting date change

The values are updated by EOC process.

5.1.4.3 Specifying Time Zone Offset

For branches with different time zones, you can define the offset time that is to be displayed in maker/checker stamp and all the reports generated for the branch.

The offset time is specified in terms of hours and minutes, and the time will be added/ subtracted from the Server Time maintained for the bank.

Hours

Specify the number of hours to be offset from Server Time to arrive at the local branch time

This is the number of hours by which the branch leads or lags behind the Server Time

Minutes

Indicate the additional minutes by which the branch leads or lags behind the Server Time

Note

The reference of time is always the System Time (Server Time)

Ahead

The system calculates the local time of the Branch by adding/subtracting the Server Time and the Time Zone Offset time. When you maintain the offset time for the time zone, you need to specify whether the system should add or subtract the offset time from the Time Zone Offset.

Checking the Ahead box indicates that the offset time is added to the Server Time. Consequently, if the box is unchecked, the offset time is subtracted from the Server Time.

Additionally, the system validates the cutoff time depending on the time you specify here. The validation is based on following 3 parameters:

- Cutoff Time maintained for the currency in Currency Definition Screen
- Cutoff Offset Time maintained for the Branch in Branch Parameters Screen
- Time Zone Offset maintained for Branch in Branch Parameters Screen

5.1.4.4 Indicating Cutoff Offset Time

When defining a currency, you can indicate a cut-off time for the currency. If your bank operates in branches located in different time zones, the cut-off time maintained for the bank will not be applicable across branches.

Therefore, you can set up an offset time for your branch based on the cut-off time set for the bank. You can specify an offset time for your branch in the Branch Parameters screen.

Hours & Minutes

The offset time is expressed in hours and minutes. The time you specify here is added or subtracted from the cut-off time maintained for the bank. This depends on the time difference between your branch and the Head Office.

5.1.4.5 Indicating Local Payments

Clearing Branch

Select the clearing branch from the adjoining option list.

Transaction Code for Consolidation Across Products

Select the transaction code for consolidation from the adjoining option list.

5.1.5 Maintaining Financial Details for Branch

You can specify the details regarding suspense GLs, Financial cycle, preference for floating rate, message generation (103,103+) for the branch in this screen. The screen appears as shown below:

The screenshot displays the 'Branch Parameters Maintenance' window. At the top, there are fields for 'Branch Code *' and 'Branch Name *', along with a 'Branch Available Status' checkbox. Below this is a tabbed interface with three tabs: 'General Details', 'Account Financial Details' (which is currently selected), and 'Duplication Check Details'. The 'Account Financial Details' tab contains several sections: 'Suspense General Ledger' with fields for Real Local Currency, Cont Local Currency, Real Foreign Currency, Cont Foreign Currency, and ATM; 'Financial Cycle' with fields for Current Cycle and Current Period; 'Referral Cut Off Time' with fields for Hours and Minutes; 'Amount Block Processing' with a field for Transaction Code for Amount Block Release; 'Revaluation / Position Transfer Details' with a dropdown for Transfer Type and fields for Transfer Branch, Position Asset GL, Position Liability GL, and Transaction Code; 'Euro Redenomination General Ledger' with fields for Conversion General Ledger and Conversion Transaction Code; 'Payment Messages' with a checkbox for 'Generate 103+' and fields for Default Bank Operation Code, Branch Code for Clearing, Clearing Through Branch, and Loan Direct Debit Generation Days; 'Floating Rate' with a checkbox for 'Proceed without maintaining float rate' and fields for Sector Code, Routing No, Deferred Statement, and Install (with a dropdown set to 'Installation Required'); and 'Suspense Batch Entry Details' with a checkbox for 'Suspense Entry Required' and fields for Suspense Transaction Code, Suspense Batch Number, Reverse Suspense Entry Days, Maximum Real Suspense Amount, and Maximum Cont Suspense Amount. At the bottom, there is a navigation bar with links to 'Preferences', 'SWIFT Address', 'Account Mask', 'CIF Range', 'Global Interdict Functions', 'Tax', 'Branch Currency', and 'Fields'. Below this is a status bar with fields for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status', along with an 'Exit' button.

5.1.5.1 **Specifying Suspense GL**

The accounting entries generated by different modules of Oracle FLEXCUBE will be passed into the specified 'Suspense GL' account if:

- The GL into which the entries are to be passed is not defined, or
- If the GL has been closed

Suspense GLs are of two types:

Real Suspense GL (Local and Foreign Currency)

The accounting entries that belong to asset, liability, income or expense GL categories will be passed to the 'Real suspense GL'. To indicate the real suspense GL for a branch, click option list and select a GL code from the option list.

Contingent Suspense GL (Local and Foreign Currency)

The accounting entries that belong to contingent asset or contingent liability GL categories will be posted to a 'Contingent Suspense GL'.

To indicate the contingent suspense GL for a branch, click option list and select a GL code from the option list.

5.1.5.2 **Specifying Euro Redenomination GL**

To facilitate the currency conversion process, you have to maintain a common Conversion GL and a Transaction Code.

The conversion GL that you specify in this screen will be identified as the common suspense GL for all balance conversions while re-denominating the currency of an account either for specific customers or for generic conversions.

In addition to the conversion GL you have to indicate a Transaction Code, which identifies conversion, related entries.

5.1.5.3 **Indicating Payment Messages**

Generate 103+

The 'Generate MT 103 + option' allows you to generate outgoing MT 103 messages in the MT 103 + format. This check box can be enabled only if you have enabled the generation of MT 103 messages as Payment Messages.

Note

The system will generate MT 103 messages as payment messages for transactions in the branch, and generate them in the MT 103 + format only if you have enabled this option in the following cases:

- For the counterparty of the transaction, in the BIC Code Maintenance
- By choosing the Generate 103+ option for currency in the Currency Definition
- For the product used by the transaction, in the Product Preferences

The system is also capable of processing incoming MT 103 messages in the MT 103 + format. During the upload process the system considers an MT 103 payment message to be of MT 103 + Format based on the presence of the STP code in the 119 field. Field 119 is present in the third block of the message i.e., {3: {119:STP}}.

Branch Code for Clearing

Indicate the code that identifies your branch in the Clearing Network. The code you specify for your branch should be the same as that defined in the Clearing Bank Code Maintenance screen.

Clearing Through Branch

If clearing transactions involving your branch are routed through another branch, specify the Oracle FLEXCUBE branch code of that branch in this field.

On the basis of the Routing Number Mask defined for your bank, and your specifications in this screen, Oracle FLEXCUBE automatically generates the Routing Number for clearing transactions involving your branch in the Routing Number field.

Loan Direct Debit Generation Days

Loan DD Generation days specifies the number of days before the schedule payment date, when a Direct Debit Contract is generated for the schedule due. This is applicable only for Loan Contracts in the local currency.

In order to facilitate the processing of loan repayments by customers who have their current or settlement accounts in some other bank of the clearing network you can initiate Direct Debits to these accounts. When a payment is due on a loan, a direct debit is generated 'Loan DD Generation Days' before the payment date.

As a result in Oracle FLEXCUBE the following entries will be passed:

| | |
|-----------|--------------------------|
| Dr | Clearing suspense |
| Cr | Dummy Settlement Account |

During liquidation which is performed on the schedule date the entries passed are as follows:

| | |
|-----------|------------------------------------|
| Dr | Dummy Settlement Account |
| Cr | Loan Asset GL / Interest Income GL |

Refer the 'Maintaining the attributes specific to PC products' chapter of the PC manual along with the Branch Parameters section of the Core Services Manual for details on processing DDs originating from a Loan.

5.1.5.4 Processing Amount Block

Oracle FLEXCUBE passes the accounting entries for releasing an amount block through the 'Transaction Code for Amount Block Release' field. The system will check whether any amount block of type CASA for a branch is in open status. If an account is in open status, the system will group the amount blocks into primary account and primary account branch. Then, the system will remove the amount block from the cover account and debit the blocked amount of the cover account to the primary account.

Transaction Code for Amount Block Release

Specify the transaction code for the release of amount block. The adjoining option list displays all valid transaction codes maintained in the system. You can choose the appropriate one.

5.1.5.5 Indicating Financial Cycle

Current Cycle

This is the code for the current financial year as defined by you in the 'Period Code' screen.

Current Period

Each financial year is divided into accounting periods called 'Period Codes' defined in the 'Period Code Maintenance' Screen (for details refer 'period Code screen'). The current accounting period of the financial year is displayed in this field.

5.1.5.6 Specifying Referral Cut-off Time

Referral refers to the process of handling customer transactions that force the accounts involved in such transaction to exceed the overdraft limit. Examples of typical transactions, which force an account to move into overdraft, are Payment and Collections, Funds Transfers, Standing Instructions or Clearing transactions. If an account is marked for referral, the details of transactions resulting in the account moving into Overdraft will be sent to the referral queue.

Hours & Minutes

In branch parameter, you have to specify the referral cut-off time for accepting / rejecting transactions in the referral queue.

In case a transaction is rejected from the referral queue after the cut-off time then system displays the override message as "Rejected after cut off time".

Note

Transactions are accepted into the Referral Queue even after cut-off time if account goes into overdraft.

Auto Authorisation

Oracle FLEXCUBE enables you to allow certain users (of your choice, depending on your requirements at your installation) to automatically authorize transactions.

To indicate applicability of automatic authorization for users of the branch, you must enable the Auto Authorization option in the Branch Parameters screen. When you do, you can then allow automatic authorization rights to the appropriate users at the branch.

For more details about automatic authorization, refer the Security Management System and Procedures user manuals.

Deferred Statement Status

This is a display field. This field indicates whether or not the Branch is ready for Deferred Statement Generation. 'Y' indicates the Branch is ready for deferred statement generation.

For further details on Referrals refer to the Processing Referrals in Oracle FLEXCUBE chapter of the Core Entities manual.

Install

Select the appropriate value from the drop-down list to indicate whether Oracle FLEXCUBE installation is complete or incomplete.

Proceed Without Maintaining Floating Rate

Check this option to indicate that floating rates should be propagated across all branches,

Sector code

Specify the Sector Code of your branch, as specified in the Clearing Bank Code Maintenance screen.

Routing No

On the basis of the Routing Number Mask defined for your bank, and your specifications in this screen for clearing and sector, Oracle FLEXCUBE automatically generates the Routing Number for clearing transactions involving your branch in the Routing Number field.

5.1.5.7 Specifying Revaluation/Position Transfer Details

You can transfer the currency positions from the individual branches to the designated branch during EOD. The system transfers the position from the existing branch to the treasury branch. When the position is negative in the given GL, then the system will choose the Offset account as Position asset GL and when the position is positive in the given GL, then the system will choose the Offset account as Position liability GL. Sequence of the EOD between the designated branch and all other branches are operationally controlled.

You can maintain the following revaluation/position transfer details:

Transfer Type

Select the transfer type from the drop-down list. Following are the options available in the drop-down list:

- Position
- Reval

Note

- If the Transfer Type field is left blank then neither the position transfer nor revaluation transfer to the designated branch will be done.
 - For position transfer, the 'Inter Branch in Local Currency' check box in the Transaction Code maintenance screen, should be checked to avoid creating position due to IB posting.
-

Transfer Branch

The system will identify the branch to which the revaluation/position transfer should be done.

During account/GL revaluation process, the system considers this branch and the GL to pass one leg of the revaluation profit and loss entries. The other leg of the entries will be passed based on the revaluation profit/loss GL and the account branch. The account branch in this case is the 'Revaluation Into' branch maintained as part of branch parameters maintenance.

Position Asset GL

Specify the GL to which the notional asset needs to be transferred..

Position Liability GL

Specify the GL to which the notional liability needs to be transferred.

Transaction Code

Specify the transaction code used to pass the accounting for position transfer.

While saving, the system will validate the difference between negotiated rate input by the user and the base rate maintained against the tolerance limit at the product level. If the difference is not within the tolerance limit, then the system will display an error message.

5.1.5.8 Specifying Suspense Batch Entry Details

Specify the following details:

Suspense Entry Required

Check this box to indicate that automatic suspense entries can be posted for a branch. If a mismatch occurs between real entries or contingent entries during the batch, then the system will post the balancing entries and will continue the EOD without interruption, if you check the 'Suspense Entry Required' option and specify the Suspense Batch Entry details. You can correct those entries manually at later stages.

If you leave this box unchecked and if a mismatch occurs in Real or contingent entries then the EOD is stopped and the error is thrown. You have to correct the entries.

Suspense Transaction Code

Specify the transaction code against which the suspense entries are posted or /reversed.

Suspense Batch Number

Specify the batch number against which the suspense entries are posted or reversed.

Reverse Suspense Entry Days

Specify the days till which the system can sustain the mismatch entries once the batch is run for the same. You can specify a value within a range of 1 to 9999.

If the 'Reverse Suspense Entry Days' is greater than the EOD suspense entry date and if reversal action is not performed for the suspense entry then the EOD is stopped and system displays an error message.

Maximum Real Suspense Amount

Specify the maximum amount that the system can consider to post suspense entry for an EOD for real entry.

Maximum Cont Suspense Amount

Specify the maximum amount that the system can consider to post suspense entry for an EOD for contingent entry.

5.1.6 Maintaining Duplication Check Details

You can maintain the number of days for which the duplication check should be done for a transaction in 'Duplication Check Details' tab. A transaction is compared with all previous transactions entered during the number of days maintained here, for any possible duplication.

The duplicate check is done starting from booking date till the booking date minus the number of days for duplicate check. This duplication check is carried out based on the combination of the preferences maintained at the FT/SI product respectively.

Note

Duplicate transaction check is applicable only for FT and SI transactions.

The screenshot shows the 'Branch Parameters Maintenance' window. At the top, there are fields for 'Branch Code *' and 'Branch Name *', and a checkbox for 'Branch Available Status'. Below these are three tabs: 'General Details', 'Account Financial Details', and 'Duplication Check Details' (which is selected). Under the 'Duplication Check Details' tab, there is a section titled 'Duplication Check Details' with a pagination bar showing '1 Of 1'. Below this is a table with three columns: 'Module', 'Duplication Check Required', and 'Duplication Days'. The 'Module' column has a dropdown menu. The 'Duplication Check Required' column has a checkbox. The 'Duplication Days' column has a text input field. At the bottom of the window, there is a navigation bar with links: 'Preferences', 'SWIFT Address', 'Account Mask', 'CIF Range', 'Global Interdict Functions', 'Tax', 'Branch Currency', and 'Fields'. Below the navigation bar, there are labels for 'Maker', 'Checker', 'Date Time:', 'Mod No', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

You can specify the following details here:

Module

Specify the module for which you wish to maintain duplicate check days or select the module from the option list provided.

Duplication Check Required

Check this box to indicate that duplication check is required for the transactions related to the module selected.

Note

- However, despite checking this box if the duplication check criteria are not specified in the following screens the system will not perform duplication checks for all the respective contracts under this branch.
 - Payments and Collection Product Category Maintenance
 - Funds Transfer Product Preference
 - Standing Instruction Product Definition
-

Duplication Days

Specify the number of days for which the duplication checks for transactions need to be carried out. Calendar days are considered for duplication check.

Note

You need to specify a value here if 'Duplicate Check Required' option is selected. You cannot specify a negative value.

5.1.7 Maintaining SWIFT Address for Branch

Click the 'SWIFT Address' in the Branch Parameters screen to invoke 'Additional SWIFT Address' screen.

The screen appears as shown below:

Branch Parameters Additional SWIFT Address

Branch Branch Name

SWIFT Addresses

1 Of 1 Go

| SWIFT Address * | Description |
|----------------------|----------------------|
| <input type="text"/> | <input type="text"/> |

Ok Exit

You can specify the SWIFT addresses related to the branch in this screen.

5.1.8 Defining Account Mask

Customer Account Masks can be defined at the Branch Level or at the Bank Level

Click the 'Account Mask' in the Branch Parameters screen to invoke 'Account Parameters' screen.

The screen is as shown below:

Account Parameters

Customer Account Mask

Checksum Algorithm

User Defined Algorithm

Customer Account

Consumer Number

Start Account Number

End Account Number

☐ Auto Generate Account

☐ Loan Account Auto Generate

Auto Account Creation

Start Account Number

End Account Number

Fund Subscription

Start Account Number

End Account Number

Ok Exit

For further details please refer the Section 'Specifying the Account generation Parameters at bank level' under Bank Parameters.

Fund Subscription

You may wish the system to automatically create deposit accounts for customers at the time of fund subscription. These system-created deposit accounts are for use as settlement accounts.

Here, you need to specify the range of numbers available for such auto created accounts by mentioning a start and an end number.

If you wish to retain the facility of auto creation of current accounts at loan initiation, you will have to ensure that the account number mask does not have any user input character.


Note

- The range of numbers specified for the creation of current accounts should not overlap with the range specified for the creation of deposit (or contra deposit) account.
 - Fund account number ranges are enabled only in the fund branch.
-

5.1.9 Maintaining Customer Number Range

You can specify a number range based on which the customers of your bank will be assigned CIF numbers for identification. Since the number range is maintained at the branch level, you can specify different number ranges for different branches of your bank.

To maintain the number range, click the 'CIF Range' in the Branch Parameters screen. The 'Customer Number Range' screen is displayed:



Specify the following in this screen:

Start Customer No.

This number is the basis on which the system generates the CIF numbers for customers of your branch.

The CIF number generation is determined by the following details:

- The CIF mask maintained in the Bank-Wide Parameters screen. Assume that the mask is 'bbbnnnnnn' (where 'bbb' represents a 3-digit branch code and 'nnnnnn' is a 6-digit number).
- The start customer no – assume that this number is 100

While generating CIF numbers, the system will automatically assign the number '000000100' to the first customer of your branch, assuming that the branch code is 000. This conforms to the CIF mask maintained for the bank. The next customer will be '000000101' and so on.

If the option 'Auto Generate CIF Numbers' is checked in the 'Bank Parameter Preferences' screen and the start CIF is zero or null, the new customer number will be generated for the branch as per the current running sequence number of the Head Office.

End Customer No

Just as you specify a Start Customer Number, you have to indicate the End Customer Number also. You will not be allowed to maintain customers beyond this range.

Let us assume that the 'End Customer No.' is 99999. As per the mask and the end number, the last customer CIF number that is generated at your branch will be '000099999'.

Start Dummy Customer Number & End Dummy Customer Number

You should also maintain a dummy customer number range in this screen. When maintaining a dummy range, you should ensure that dummy CIFs and the actual range do not overlap with one another.

The dummy CIF range will be used for account number generation. As explained earlier, the account number can be generated based on the following account mask:

'bbbTZCCCCCSD'

Where,

- bbb – is the branch code
- T – indicates the account code
- Z – is the currency type
- CCCCCC – is the CIF number of the customer
- S – is the sequence number for a combination of account code, currency type and customer
- d – is the control number generated by 'Modulo 11 with Weights' algorithm (explained earlier)

To recall, the sequence number that is automatically generated by the system is for an account code + currency type + customer combination. The sequence number is a single digit number (from 1 to 9). This means that, for the same combination, you will be allowed to maintain only nine accounts. To eliminate this limitation and to allow maintenance of more than nine accounts for the same combination, the dummy customer number range will be utilized. This is explained with the help of an example.

For example, Assume that you have maintained the following CIF range for your branch:

| | |
|-----------------|--------|
| Start CIF No. | 100000 |
| End CIF No. | 198999 |
| Start Dummy No. | 199000 |

| | |
|---------------|--------|
| End Dummy No. | 199999 |
|---------------|--------|

Ms. Jennifer approaches your bank to open a savings account in your branch (branch code is '000'). Further, the CIF and account number masks maintained for the branch are 'bbnnnnnn' and 'bbbTZCCCCCSd' respectively.

As per the CIF mask, Ms. Jennifer is assigned the CIF number: 000123456. According to the account number mask, the 6th to 12th digits will be the last six digits of the CIF number, which is '123456'.

The account number of the first savings account, in USD opened for Ms. Jennifer is: 000411234561 (we will consider only 12-digits for this example since the 13th digit is auto generated by the system based on Modulo 11 with Weights algorithm).

The components of the account number **000-4-1-123456-1** are as follows:

- 000 – is the branch code
- 4 – is the account code
- 1 – is the currency type
- 123456 – is the CIF number for Ms. Jennifer
- 1 – is the sequence number for the combination of account code, currency type and customer i.e. the number '4-1-123456' will be common for the first 9 accounts maintained for the same combination.

Now, Jennifer decides to open another account for the same combination. In this case, the sequence number gets incremented to 2 and the account will be assigned the number: **000-4-1-123456-2**.

This will go on till the 9th account for the same combination. The 9th account number would be **000-4-1-123456-9**.

If the customer decides to maintain the 10th account for the same combination, the sequence number will restart since it has reached the maximum allowed level. This would result in duplication of account numbers. To eliminate this, the system will now use the dummy CIF range to number the accounts.

Therefore, the 10th account number will be: **000-4-1-199000-1**. This sequence will continue for subsequent accounts maintained for the same combination.

Note

You can view all the dummy CIF numbers linked to a customer in the 'Customer Accounts – Allocated Dummy CIF' screen.

5.1.10 Maintaining Global Interdict Functions

Click 'GI Functions' button in the Branch Parameters Maintenance screen to invoke 'Branch Global Interdict Functions' screen. Using this screen, you can integrate with Global Interdict

System for online verification of transactions before authorisation in order to comply with 'Office of Foreign Assets Control' (OFAC) regulations in US.

5.1.11 Maintaining Preferences

To specify your preferences, click 'Preferences' button from the 'Branch-Wide Parameters' screen. The 'Preferences' screen is displayed.

In this screen you define the following preferences:

- The netting suspense GL into which settlement entries for netted FX Contracts should be posted
- The CIF Number against which all Walk in customers should be identified
- The format in which the IBAN Account Number and the Bank Code should be captured
- The duration for which spool files should be stored in the spool file directory
- The directory into which the files should be spooled
- MIS codes for posting of automatic balancing entries

These details can be maintained by the respective branches. For a branch you maintain the following, in the 'Preferences' screen:

Netting Suspense GL

All settlement accounting entries relating to a netted FX contract, is passed into the specified 'Netting suspense GL'. The net amount of the settlement is transferred through the Nostro accounts. For instance, let us take the following two outstanding contracts entered into by bank A; both settling on January 10, 1998:

- Bought from bank B 1 Million USD in exchange for 35 Million INR
- Sold to bank B 1/2 million USD in exchange for 18 million INR

The above contracts can be settled in either of the two ways given below, on the settlement date:

- Settle both contracts separately
- Net the settlements of the two contracts

If your bank has a netting agreement with the counterparty, the settlement entries are posted to this 'Netting suspense GL' and the net amounts are settled through the nostros.

Walk in Customer

For your branch you can create a walk in customer ID against which you track all those customers who do not hold a regular account with your bank but have approached the bank for a transaction, say, for encashment of traveler's checks or for manager's checks.

Internal Swap Customer

You need to specify an internal swap customer for processing internal swaps. The names of all the customers of your bank will be displayed in the option-list provided. This will be a unique customer meant for processing internal swaps.

Clearing Account

Specify the default GL account to be used for clearing transactions at the branch.

Offset Clearing Account

Specify the default offset GL account to be used for clearing transactions at the branch.

Weekly Holiday 1 & 2

Using this option you can indicate the holiday in a week for your branch. You can select the day for holiday from dropdown list. If you want to set only one holiday in a week for your branch, select the day for Weekly Holiday 1 and leave Weekly Holiday 2 Blank. If you want to opt for two holidays in a week, select the days for Weekly Holiday 1 & Weekly Holiday 2.

Clearing Bank Code

Specify the code by which your bank is identified in the Clearing Network you participate in. This has to be the same as that specified for your bank in the Clearing Bank Code Maintenance screen.

MIS Group for Currency (Mismatch Entries)

If the posting of automatic balancing entries due to currency and value date mismatches has been specified for your bank, you can specify the MIS codes or groups to be used for posting the balancing entries.

Interdict Validation Required

For your branch you need to indicate whether Interdict Validation is required for all Customers, Customer Accounts, Funds Transfers, Standing Instructions, Foreign Exchange, Letter of Credit and DD transaction processed within your branch.

The options available are:

- Yes – the details of CIFs and Customer Accounts, captured in the specific branch of your bank will be sent to the GI system as and when they are captured in Oracle FLEXCUBE.
- No – the details maintained in the specific branch will not be sent to the GI system for online verification.

Interdict Timeout Interval

If you indicate that the details should be sent to the GI system, you will also have to specify the interdict timeout interval period. If the response time from the GI system takes longer than the time that you specify in this field, the transaction will be timed out since the processing time exceeds the time stipulated in this field.

If you enable this preference, you will have to identify the Code or ID of the function in Oracle FLEXCUBE for which such a validation should be performed by clicking on the 'GI' button in the Branch Parameters screen.

Status Processing Basis

In the Branch Parameters, you can indicate the basis upon which status processing must be done at the branch, for customer accounts as well as loan contracts.

Status processing can be done either at an individual contract / account level, or at a Group / CIF level.

If you opt for Group / CIF -level processing, it is done in two stages:

- The worst status among all contracts and accounts under a specific customer group or CIF is arrived at
- All accounts and contracts involving the customer group or CIF are then moved to the worst status that was arrived at

If you opt for status processing at individual contract / account level, the status of each contract or account would be assigned according to the status processing parameters that are operative for the contract or account.

If 'Status Processing' is at Individual Contract Level, then you can change the status and trigger the status change event along with accounting entry posting. However if the 'Status Processing' is at CIF/Group level individual module (LC, CI, MO, CA, IA and BC) batches will be updating common storage with the derived status of each contract and CIF/Group level status will be triggered by the common status change batch. The common status change batch will call the individual module function for status change processing.

For details about loan status processing and provisioning, consult the Loans user manual and the Core Entities user manual.

Provisioning Frequency

Provision processing depends upon status processing for accounts and contracts. The provisioning batch process executes after the status processing batch. If status processing is indicated to be processed at group / CIF level, you can indicate the frequency at which the provisioning batch is to be executed for your branch. The frequency options available are daily and monthly.

For details about loan status processing and provisioning, consult the Loans user manual and the Core Entities user manual.

(Withdrawable) Uncollected Funds Basis

You can define how the System enforces the allowable amount of uncollected funds (on an account) that can be withdrawn within a business day.

For each customer account, you designate a limit on the amount of uncollected funds that can be withdrawn (the Uncollected Funds Limit). You can also indicate whether, for a given business day, the System should consider the uncollected funds that are allowed to be withdrawn as:

- The funds scheduled to be released on the current date (today), OR,
- The total uncollected funds available against the account subject to the Uncollected Funds Limit

You can specify your preference by choosing any of the following options:

- **Uncollected Funds :** If you select this option, an amount up to or less than the uncollected funds limit defined for the account, is allowed to be withdrawn, on a given business day.
- **Uncollected Funds Available Same Day:** If you select this option, the funds allowed to be withdrawn against uncollected funds on a given business day are the funds scheduled to be released on the current date (today).

Deferred Statement Generation

Check this option to stop the automatic account statement generation at end of day.

If this option is checked, then the account statement generation will be deferred to whenever you initiate action for executing Batch Operations for statement generation. You can do this through the Branch Statement Status Change screen.

Enterprise GL

Check this option if this branch needs to have an enterprise GL hand-off. Once checked the system will identify the said branch for creating an ASCII hand-off file containing the relevant accounting entries to be sent to the external enterprise GL.

Minor Age Limit (Yrs)

Specify the minor age limit. This varies from nation to nation. However If user does not maintain the age limit, the system will automatically defaults it as 18 years during save.

Notification Days

Specify the intimation days to send advice prior to the customer turns major based on DOB.

Cheque Stale Days

Specify the cheque stale days. Here you can identify the number of days for which stale validation is done.

Limit Expiry Advice Notification Days

Specify the limit expiry advice notification days. The system will send advice to the customer these many days before the limit expiry date.

The limit expiry advice generated by the system provides information on the limit details. Multiple lines can be attached to a customer with different expiry dates. Advice sent to the customer contains the details of the line which is about to expire.

5.1.11.1 Specifying Back-Valued Details

For your branch you can specify the maximum period up to which back valued posting can be processed. This restriction can be made applicable by specifying the following preferences:

Back Value Check Required

It is used to indicate whether all back-valued transactions should be validated against a specific period.

Back Value Days

If you enable the Back Value Check Required option, you must indicate the number of calendar days up to which back-valued transactions can be allowed. During transaction processing you will be allowed to post back-valued transactions up to the specified date in the past (no check will be done). Further, if the option is checked but you have not maintained the 'Back Value Days' (maintained as NULL), the system will interpret it to be 'Zero' days allowed (for back valued transactions).

The restriction for the maximum period up to which back-valued posting can be allowed, will be made on transactions processed in following modules:

- Payment and collections
- Data Entry
- Retail Teller
- Utility Payments
- Foreign Exchange
- Money Market
- Expense Processing
- Fund Transfer
- Loans and Deposits

While saving transactions pertaining to any of these modules the System validates the Value Date of the contract to check whether it adheres to the restriction. You will be intimated with an override if the Value Date is earlier than the specified period. This restriction is made applicable on all uploads as well.

Refer the Contract Processing chapter of the individual modules for additional information.

5.1.11.2 Indicating Profit and Loss Adjustment

Track Previous Year Profit and Loss Adjustment

You can collect data pertaining to the unrealized income booked for each contract during the year by triggering the Year-end batch process. But, you will be allowed to trigger the batch process for splitting the unrealized profit and loss for the previous year and the current year only if you have specified this (Track PY PnL Adjustment) as a preferred option for your branch.

If you set this preference, the data pertaining to the unrealized income is collected at contract level for the following modules:

- Securities - Unrealized Interest, Discount and Premium accrued for the year.
- Derivatives - unrealized income
- Bills and Collections - unrealized income
- Letters of Credit - unrealized income
- Money Markets - unrealized income

5.1.11.3 Indicating Revaluation Split Details

Revaluation Split Required

You can choose to break-up revaluation profit/loss into:

- Trading P&L – P&L due to revaluation of foreign currency transactions during the day
- Revaluation P&L – P&L due to revaluation of opening balances (balances without current day's turnover)

If you enable this preference, all GLs which are marked for revaluation split will have their revaluation profit/loss broken up into trading and revaluation P & L for entries posted from this branch.

For further details on Split Revaluation refer the GL user manual.

5.1.11.4 Specifying Suspense Product Maintenance

When a branch goes offline, user posts the transactions allowed in offline mode. Once the branch and host are online, branch starts posting these transactions as force post. If the force post fails, then the host needs to post these transactions as a suspense product in the branch.

Debit Product

Specify a valid debit product you need to maintain as Suspense Product. The adjoining option list displays all the valid debit products maintained in the system. You can select the appropriate one.

Description

The system displays the description based on the selected debit product

Credit Product

Specify a valid credit product you need to maintain as Suspense Product. The adjoining option list displays all the valid credit products maintained in the system. You can select the appropriate one.

Description

The system displays the description based on the selected credit product.

5.1.11.5 Specifying International Banking Account Number MASKS

The IBAN or International Bank Account Number is a unique account number that is used to identify a customer's account in a financial institution internationally.

International Bank Account Numbers in your bank are generated in the format of the account mask that you specify in the Branch Parameters screen. Therefore, you have to first define IBAN masks.

The IBAN Mask

Since IBANs should be maintained in a particular format you should first define the format in which the IBAN should be captured. You should also indicate the format in which the bank code of the bank in which the account resides should be maintained.

The maximum length of an IBAN should be 34 characters. The IBANK Mask should be a combination of the following parameters:

- An **ISO Country Code**, which has a maximum length of two characters. The identifier that you can use to indicate the country code is DD. The identifier will be replaced by the actual country code while defining the account number. For instance, you will replace DD with PL for Poland, US for the United States and so on.
- A **Check Digit Number** calculated according to an ISO Standard algorithm, using the Country Code, Bank Code and Account Number combination. Since this is a two-digit number you can use the identifier CC to specify this algorithm. The system arrives at and replaces this identifier with the actual check-digit based on the Country Code, Bank Code and Account Number combination.
- The **Bank Code** of the bank where the IBAN resides. This code is assigned to the respective Bank by its national bank. There are no individual restrictions on the length of Bank Code and Account Number. However, the combined length of the Bank Code and Account Number should not exceed 30 characters. You can use the identifiers **a** (for alphabets) and **n** (for numerals) as the identifiers to capture the length of the bank code.
- The **Account Number** of the customer account. The bank in which the customer account resides assigns this number. You can use the identifiers **a** (for alphabets) and **n** (for numerals) as the identifiers to capture the length of the account number.

For example, you maintain an IBAN mask in the following format:

DDCCaaaaaaaannnnnnnaaaaaannnnnnnnnn

While capturing the IAB number you have to strictly adhere to the format mentioned above.

USccCHASEBANK000101CBNYLI450000026

In place of the 'cc's the system will generate the check digit algorithm based on the Country Code, Bank Code and Account Number combination.

The Bank Code Mask

After indicating the IBAN mask you have to specify the mask for the Bank Code. The Bank Code mask is a combination of alphabets and numerals. Therefore you can specify **A** and **N** as the identifiers. Subsequently, while capturing the bank code in the IBAN screen each of these characters will be replaced with the respective alphabet or numeral. For instance, let us assume that you have maintained a 15-character mask for the Bank Code:

| | | | | | | | | | | | | | | |
|---|---|---|---|---|---|---|---|---|---|---|---|---|---|---|
| A | A | A | A | A | A | A | A | A | N | N | N | N | N | N |
|---|---|---|---|---|---|---|---|---|---|---|---|---|---|---|

You will have to capture the corresponding bank code in the same format:

| | | | | | | | | | | | | | | |
|---|---|---|---|---|---|---|---|---|---|---|---|---|---|---|
| C | H | A | S | E | B | A | N | K | 0 | 0 | 0 | 1 | 0 | 1 |
|---|---|---|---|---|---|---|---|---|---|---|---|---|---|---|

Note

The combined length of the Bank Code and Account Number should not exceed 30 characters.

5.1.11.6 Indicating Cheque Number Mask

Cheque Number Mask

The system displays the cheque number mask maintained at bank parameter level.

The 'Cheque Number Mask' defined at branch parameter level cannot be changed once maintained and authorized.

If the cheque book is issued to non base branch accounts, the system populates or validates the cheque numbers based on the cheque mask of the account branch.

5.1.11.7 Indicating ELCM Integration

Check this box to indicate that the branch details will be replicated to ELCM system. System will select this option by default, but you can unselect it.



System will not allow unselecting this option once it is selected.

LDAP DN Template

The LDAP DN template needs to be maintained here for each branch. This is used in Oracle FLEXCUBE user maintenance form to populate corresponding LDAP user-id automatically from the template.

5.1.12 Maintaining LCY Message Preference for Branch

Click the 'LCY Msg Pref' button in the Preferences screen to invoke the 'LCY Message Preference' screen.

The screen is as shown below:

| Module * | Module Description | Local Currency Message Type |
|-------------------|----------------------|-----------------------------|
| [Selected Module] | [Module Description] | [Drop-down Menu] |

Branch

The system displays the branch details.

Description

The system displays the description.

Module

Specify the module details.

Module Description

Specify the description of the module.

Local Currency Message Type


Select the local currency message type from the drop-down list. Following are the options available in the drop-down list:

- Suppress LCY
- Generate LCY Message Thru SWIFT
- Generate PC Contract

5.1.13 **Specifying UDF Details**

You can associate values to all the User Defined fields created and attached to the Branch Parameters Screen. You can view the list of User Defined fields associated by clicking the 'Fields' button.

The screen appears as shown below:



| Field Name | Value | Value Description |
|------------|-------|-------------------|
|------------|-------|-------------------|

You can enter the value for the UDFs listed here in the 'Value' column.

For more details on how to create user Defined fields, refer chapter 'Creating custom fields in Oracle FLEXCUBE' in the User Defined Fields User Manual under Modularity.

5.2 **Maintaining Tax Cycle**

You can maintain tax cycle at the bank level through the 'Tax Cycle Maintenance' screen. Invoke this screen by typing 'STDTCYCL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Tax Cycle Maintenance

New Enter Query

Tax Cycle *
Description
Start Date *
End Date *

Fields

| Input By Date Time | Authorized By Date Time | Modification Number |
|-----------------------|----------------------------|----------------------------------------------------------------------|
| | | <input type="checkbox"/> Authorized <input type="checkbox"/> Open |

Tax Cycle

You need to define the tax cycle, which will be uniquely identified in the system

Start and End dates for tax cycle

You need to indicate the start and end date of the tax cycle you are defining, using the adjoining calendar.

5.2.1 Updating Tax Cycle

The Current Tax Cycle would be updated as and when the tax cycle changes. This would be done during authorization of date change function on the first day of the new Tax Cycle.

5.2.2 Maintaining Tax

To maintain Tax parameters at the branch level, click the 'Tax' button in the Branch Parameters Details screen.

The screen appears as shown below:

Branch Parameters Tax Maintenance

Tax Cycle

☐ Consolidated Certificate Required

☐ Individual Certificate Required

Tax Certificate Frequency

Frequency Value

Ok Exit

Tax Cycle

This is the current tax cycle for the branch. This is a display field. Whenever the tax cycle changes, the field is updated during the date change authorization for that day.

Consolidated Tax Certificate Required

Check this option to indicate Consolidated Tax Certificate is required for all the transactions done in the Tax Cycle. This option works in conjunction with a similar option in the Customer Information Maintenance and the Tax Category Maintenance screen.

The Consolidated Tax Certificate would be generated at the frequency specified at the branch level. Apart from this, the certificate would also be generated at the end of the Tax Cycle. The consolidated tax certificate would always display all the transactions pertaining to the current Tax Cycle.

Individual Tax Certificate Required

Check this option to indicate Individual Tax Certificate is required for individual transactions under the selected tax category. This option works in conjunction with a similar option in the Customer Information Maintenance and the Tax Category Maintenance screen.

Tax Certificate Frequency

This field is enabled only if the Consolidated Tax Certificate option is checked.

You need to specify the frequency with which the tax certificate should be generated. This would be a combination of the Tax Certificate Frequency and the Tax Certificate Day. It could be any of the following:

- Monthly - This indicates that the tax certificate would be generated every month. The day of the month on which the Tax Certificate would be generated is defined in the Tax Certificate Day field.
- Quarterly (Q) – This indicates that the tax certificate is generated once in three months. The end-month for the first quarter is defined in the Tax Certificate Day field. The Certificate would be generated on the last working day of the month defined in the Tax Certificate Day field. Subsequent end-months would be derived by the system.
- Half Yearly (H) – This indicates that the Tax Certificate would be generated once in six months. The end-month for the first half-year period is defined in the Tax Certificate Day field. The Certificate would be generated on the last working day of the month defined in the Tax Certificate day field. Subsequent end-months would be derived by the system.

- Yearly (Y) – This indicates that the tax certificate would be generated once a year. The month in which the certificate needs to be generated is defined in the Tax Certificate Day field. The Certificate would be generated on the last working day of the month defined in the Tax Certificate Day field.

Frequency Value

Select the appropriate month for tax certificate generation, from the adjoining drop-down list.

5.2.3 Maintaining Clearing Currencies

You can maintain a list of currencies in which clearing transactions can be processed under a branch. In order to achieve this, you need to invoke the 'Clearing Currency' screen by clicking the 'Branch Currency' button in the 'Branch Parameters – Detail View' screen.

Here you can capture the following details:

Branch Code

The branch code gets defaulted from the 'Branch Parameters – Detail View' screen. A brief description of the branch is displayed alongside.

Currency Code

Specify the currency in which you wish to allow clearing transactions under this branch. You can specify multiple currencies for a branch. Click on the adjoining option list and select the appropriate code from the list of currencies maintained in the system.

Currency Description

A description of the chosen currency code is displayed here

5.2.4 Account Statement Handoff

The account statement handoff will consider the movements on accounts based on the Statement Date and not the Transaction Date. The Statement Status Change will itself run the Account Statement handoff for the previous working date before marking the Branch Statement Status as ready.

5.2.5 Account Statement Generation

Accounting entries with Statement Date lying between From Date and To Date populated in the handoff records will be picked up for Account Statement Generation processing.

5.3 Maintaining Role to Head Mapping at Branch Level

You can maintain different General Ledgers for different branches for the accounting roles defined in the system. If you have maintained Role to Head mapping for a product at the branch level, the system uses these accounting heads instead of the heads maintained at the product level.

You can maintain Role to Head mapping for a combination of branch, product and status in 'Branch Level Role to Head Mapping' screen. You can invoke this screen by typing 'CSDACRHM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Branch Level Role to Head

New Enter Query

Branch *
Branch Name
Product Code *
Product Description
Status *

Role To Head Mapping Details

1 Of 1 Go

| Accounting Role * | Accounting Head * |
|-------------------|-------------------|
| | |

Fields

Maker
Checker
Mod No
Date Time:
Date Time:
Record Status
Authorization Status

Exit

You can specify the following details in this screen:

Branch Code

The branch code of the current branch gets defaulted here.

Branch Name

The name of the current branch corresponding to the branch code gets displayed here.

Product Code

Specify the product code for which you wish to maintain role to head mapping or select the product code from the option list provided.

Status

Specify the status code for which you wish to maintain role to head mapping or select the status code from the option list provided.

Accounting Role

Select the accounting role to be used for role to head mapping, from the option list provided.

Accounting Head

Select the GL accounting head to be used for role to head mapping, from the option list provided.

You can add more rows to accounting role and heads by clicking the 'plus' icon provided. You can also delete a row from this table by selecting the required row and clicking the 'minus' icon.

Note

The accounting roles and heads maintained here will override the default role head mapping maintained for the product.

5.3.1 Viewing Accounting Role to Head Mapping Details

You can view the details related to accounting roles and heads for a branch in 'Branch Level Role to Head Mapping Summary' screen. You can invoke this screen by typing 'CSSACRHM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Branch level Role To Head Mapping Summary

Search Advanced Search Reset Clear All

Case Sensitive

Authorization Status Record Status

Branch Product Code

Status

Records per page 15 1 Of 1

| | Authorization Status | Record Status | Branch | Product Code | Status |
|--------------------------|----------------------|---------------|--------|--------------|--------|
| <input type="checkbox"/> | | | | | |
| <input type="checkbox"/> | | | | | |
| <input type="checkbox"/> | | | | | |
| <input type="checkbox"/> | | | | | |
| <input type="checkbox"/> | | | | | |
| <input type="checkbox"/> | | | | | |
| <input type="checkbox"/> | | | | | |
| <input type="checkbox"/> | | | | | |
| <input type="checkbox"/> | | | | | |
| <input type="checkbox"/> | | | | | |
| <input type="checkbox"/> | | | | | |
| <input type="checkbox"/> | | | | | |
| <input type="checkbox"/> | | | | | |
| <input type="checkbox"/> | | | | | |
| <input type="checkbox"/> | | | | | |

Exit

The following details get displayed in this screen:

- Authorization status
- Record status
- Branch code
- Product code
- Status

6. Account Branch Transfer

6.1 Introduction

You may get request from the customers for change of account branch. Oracle FLEXCUBE allows you to transfer a customer account from one branch of the bank to another. You can also transfer the all accounts that belong to an account class to a different branch at once. This chapter explains the required maintenances and the methods to process account branch transfer.

6.2 Maintaining Branch Transfer Parameters

OLE_LINK6OLE_LINK5OLE_LINK6OLE_LINK5In order to facilitate this, you need to maintain the branch transfer parameters using 'Branch Transfer Parameters Maintenance' screen. To invoke this screen, type 'CSDACTRP' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

| Fields | | | | | |
|---------|--|----------------------|--|--|--|
| Maker | | Date Time: | | | |
| Checker | | Date Time: | | | |
| Mod No | | Record Status | | | |
| | | Authorization Status | | | |

Specify the following details:

Transaction Code

Specify a unique transaction code. The system will use this transaction code to post the accounting entries while processing the account balance transfer from one branch to another.

Note

Ensure that the options 'Account Activity', 'Cheque Mandatory', 'IC Transaction Count', 'IC Turnover Inclusion' and 'IC Penalty' are not checked on 'Transaction Code Maintenance' screen.

Transfer Bridge GL

Specify the bridge GL to be used while moving the account balance from one branch to another.

Process Mode

Specify the mode of processing the account transfer. The drop-down list displays the following options:

- I Sequential – If you choose this, the system will process the transfer in a sequential order
- I Job – If you choose this, the system will process the transfer as job

Choose the appropriate one.

Number of Parallel Jobs

Specify the number of parallel jobs. This is the maximum number of jobs that may be submitted for processing at the same time.

Commitment Frequency

Specify the commitment frequency. While processing the transfer batch, the system will perform commits based on the frequency set here.

6.3 **Transferring Customer Account Branch**

Using Oracle FLEXCUBE, you can transfer a customer account from one branch of the bank to another. The account branch transfer is processed using 'Account Transfer' screen. To invoke this screen, type 'CSDACCTR' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

Bank Transfer

New Enter Query

Transfer ID * Target Branch *
Current Branch * Target Branch Name
Current Branch Name
Transfer Date *

1 Of 1 Go

| Account Number | Account Description | Customer Number | Customer Name |
|----------------------|----------------------|----------------------|----------------------|
| <input type="text"/> | <input type="text"/> | <input type="text"/> | <input type="text"/> |

Fields

Maker Date Time:
Checker Date Time:
Mod No Record Status
Authorization Status

Exit

Specify the following details:

Transfer ID

The system generates a unique transfer ID. This will be used as a unique identifier of the account transfer.

Current Branch

Specify the current branch of the account. On processing the transfer, the system will move the account from this branch to the target branch.

Current Branch Name

The system displays the name of the current branch.

Target Branch

Specify the target branch code. The option list displays all valid branch codes maintained in the system. Choose the appropriate one.

On processing the transfer, the system will move the account from the current branch to the branch selected here.

Target Branch Name

Based on the branch code selected, the system displays the name of the target branch.

Transfer Date

Specify the effective date of the account branch transfer. Click the date button to choose a date from the calendar.

The transfer date must be a date in the future. You cannot process the transfer on the current date or a past date.

Account Details

You need to specify the following account details:

Account Number

Specify the account number that you need to transfer. The option list displays all valid account numbers at the selected branch. Choose the appropriate one.

Account Description

Based on the account selected, the system displays the description.

Customer Number

Based on the account selected, the system displays the customer number.

Customer Name

Based on the customer number selected, the system displays the name of the customer.

Once you have captured the details, save the record. The system will process the account transfer on the transfer date.

6.3.1 Viewing Account Branch Transfer Details

You can search and view the details of account branch transfer using 'Branch Transfer Log' screen. To invoke this screen, type 'CSDACLOG' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

Branch Transfer Log

New Enter Query

Transfer Reference Number

Account Number

Transfer Date

Customer No

Source Branch

Target Branch

Status

Account Class

Error Details

1 Of 1 Go

| Error Code | Error Message |
|----------------------|----------------------|
| <input type="text"/> | <input type="text"/> |

Exit

You can search for the account transfer details based on one or more of the following parameters:

- | Transfer ID
- | Account number
- | Transfer date
- | Customer number
- | Source/current branch
- | Target branch
- | Status of the transfer record (Success/Error)
- | Account class

Once you have set the search parameters, click search button. The system displays the account transfers that match the search criteria. Double-click a record to view the details.

Note

The system will not process the account transfer in the following circumstances:

- The account is a Nostro type account
 - Local currency of the current branch and the target branch are different, in case of individual account transfer
 - Minor age limit is different for the current branch and target branch
-

Note

- Staff restriction, account class restriction and branch restriction are applicable while maintaining details of individual account transfer.
 - You can mark for rerun the accounts with status 'Error' by clicking 'Resubmit' button. Such accounts are processed during EOD operations on the next day.
-

6.4 Transferring Account Class

You can transfer all accounts that belong to an account class, from one branch to another, using 'Account Branch Class Transfer' screen. To invoke this screen, type 'CSDACLTR' at the top right corner of the Application toolbar and click the adjoining arrow button.

Account Class Branch Transfer

New Enter Query

Transfer ID *
Account Class *
Account Class Description
Current Branch Code *
Current Branch Name

Target Branch *
Target Branch Name
Transfer Date *

Fields

Maker
Checker
Mod No

Date Time:
Date Time:
Record Status
Authorization Status

Exit

Specify the following details:

Transfer ID

The system generates a unique transfer ID. This will be used as a unique identifier of the account class transfer.

Current Branch Code

Specify the current branch of the account class. On processing the transfer, the system will move the accounts that belong to the selected account class from the current branch to the target branch.

Current Branch Name

The system displays the name of the current branch.

Target Branch Code

Specify the target branch code. The option list displays all valid branch codes maintained in the system. Choose the appropriate one.

On processing the transfer, the system will move the accounts that belong to the selected account class from the current branch to the target branch selected here.

Target Branch Name

Based on the branch code selected, the system displays the name of the target branch.

Transfer Date

Specify the effective date of the account branch transfer. Click the date button to choose a date from the calendar.

The transfer date must be a date in the future. You cannot process the transfer on the current date or a past date.

Account Class

Specify the account class that you need to transfer. The option list displays all valid account classes maintained in the system. Choose the appropriate one.

Account Class Description

Based on the account class selected, the system displays the account description.

Once you have captured the details, save the record. The system will process the account transfer on the transfer date.

6.5 Processing Account Branch Transfer

During Beginning of Day Operations, the system will check the accounts whose transfer date is the current system date. These accounts are processed by the account branch transfer batch (ACDTRFBT), which is triggered as part of BoD operations.

The system verifies the balances of the accounts to be processed. There can be two cases as follows:

- I Negative balance – If the account balance is negative, then the system will debit the transfer GL and credit the account to make the balance zero.
- I Positive balance – If the account balance is positive, then the system will debit the account and credit the transfer GL to make the balance zero.

Further, the system updates the remaining necessary account information. The new branch code is updated in messages, statements and all branch related information specific to the account.

Note

The system will not process the account transfer in the following circumstances:

- The target branch is not allowed for the account class
 - The account has uncollected, unauthorized or tanked balance
 - The account status is 'Frozen', 'Deceased', 'No Debit' or 'No Credit'
 - The account is a Nostro type account
-

Once the details are updated, the system transfers the balance back to the account from the transfer GL.

Auto deposits linked to the account is handled as follows:

- I Auto deposit maturing on the transfer date – The system does not transfer the auto deposits that mature on the date of transfer.
- I Auto deposit maturing in the future – The system transfers the auto deposits that mature on a future date.

In case of a customer portfolio transfer or a bank merger, the accounts will be transferred to the corresponding branch. For further details on customer portfolio transfer and bank merger, refer to the sections 'Transferring Customer Portfolio' and 'Merging of Branches' in chapter 'Branch Transfer of Loans' of Retail Lending user manual.

7. System Dates Maintenance

7.1 Introduction

In the 'System Dates Maintenance' screen you maintain the system dates for your branch, for instance, the business date for your branch, which is the booking, date for all transactions input in the branch.

The dates screen is maintained at the branch level by the respective branches. Invoke this screen by typing 'STDDATES' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

System Dates Maintenance

New Enter Query

Branch Code *

Today

Previous Working Date

Next Working Date

Fields

| Input By Date Time | Authorized By Date Time | Modification Number |
|-----------------------|----------------------------|-------------------------------------|
| | | <input type="checkbox"/> Authorized |
| | | <input type="checkbox"/> Open |

In this screen the following fields are maintained for your branch:

You define today's date, previous working date and next working date, for the first time, during installation of the system (for details refer to the installation manual).

Suppose Oracle FLEXCUBE is installed on 1 January 1998, in your bank. In the dates screen you would input the following:

Today's date: 01-JAN-1998

Previous working date: 31-DEC-1997

Next working date: 02-JAN-1998

After EOD for a branch is run, the system will not allow you to run any other operation in the branch, till a date change has been invoked.

If you try to run any other application, you will be prompted to invoke a date change first.

- I Simultaneously two different branches can be running on two different system dates. This may happen when EOD for a branch is delayed for some reason.

- I Based on 'today's date' (post authorization) the system computes and updates the 'Current financial cycle' and the 'Current period' in the Branch Parameters screen.

7.1.1 Maintaining Dates Change

For maintaining date change, invoke the 'System dates maintenance' screen after EOD for the day is run. Click 'Unlock' in the Action menu or click unlock icon. The system populates the default dates in the screen.

For instance, on the first working date i.e., 2nd of January, 1998; the system dates will be updated to:

Today's date = 02-Jan-1998

Previous working date = 01-Jan-1998


Next working date = 03-Jan-1998

'Today's date' is defaulted from 'Next working date' of the old record. 'Previous working date' is defaulted from 'today's date' of the old record. The 'Next working date' is picked up from the 'Local branch holiday calendar' as maintained by you. You can modify 'today's date' and the 'next working date' by either clicking unlock icon on the toolbar/selecting 'unlock' from the action menu.' Previous working date' cannot be modified.

Today's date, if modified, should always be greater than the 'previous working date' and less than the 'next working date'. Similarly, 'next working date' if modified should be greater than 'today's date'. On modifying the dates, the system will ask you for an override. On confirmation the change will be effected.

Date change should be immediately authorized because no application of Oracle FLEXCUBE can be run without date change authorization.

- I If you have input any date modification, you cannot authorize it. A user with a different login ID should do it.
- I For a branch you can have only one system dates record
- I Any modification in date, (be it an authorized or unauthorized record), can be done any time after today's EOD and before BOD for the next day is run. You can modify the 'next working date' any time before running the EOD for the current day.

To authorize, click authorize icon on the toolbar. If any modifications were made, on the system date, the old and the new values will be displayed. After which an alert box will warn you that the dates change will be authorized. You will be prompted to confirm. Click  to confirm. The change will be authorized. If you do not want to authorize the change then click delete icon, you will be returned to the screen from where you invoked the authorization function. Click 'Exit' button to exit and return to the Application Browser.

8. Web Service Maintenance

8.1 Introduction

Oracle FLEXCUBE supports a generic functionality to call external web services. The operations done on the screens have the information of web services. The request processed during the operations is analyzed and the web service is enabled. This chapter takes you through the WebService Maintenance, WebService Mapping and other details regarding WebService.

8.2 Maintaining Web Service

You can maintain Web service through WebService Maintenance screen. You can invoke this screen by typing 'CSDEXTWS' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Webservice Maintenance' application window. It features a toolbar with 'New' and 'Enter Query' buttons. The main content area is divided into two columns of input fields. The left column includes 'WebService Code *', 'WebService Description', 'WebService User *', and 'WebService Password *'. The right column includes 'WebService Server IP *', 'WebService Server Port *', and 'WebService Server URI *'. The bottom of the window has a blue footer bar containing labels for 'Maker', 'Checker', 'Mod No', 'Date Time:', 'Record Status', 'Authorization Status', and an 'Exit' button.

Specify the following here:

WebService Code

The unique code for the web service s defaulted here.

WebService Description

The description of the web service is displayed here.

WebService User

The system displays the user of the web service.

WebService Password

The system displays the password with which the web service is invoked.

WebService Server IP

The system defaults the IP address of the server where web service is installed.

WebService Server Port

The system displays the port of the server where web service is installed.

WebService Server URI

The system defaults the URI of the server where web service is installed.

8.2.1 Mapping of Web Service

WebService mapping is attached to the transaction screens for which web service call is required. You can invoke this screen by typing 'CSCEXWSO' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

| WebService Code | Calling Sequence Number | Calling Stage | Status | Details |
|-----------------|-------------------------|---------------|-------------|-------------------------|
| | | PRE | Unprocessed | Details |

WebService Code

Select the unique web service code from the adjoining option list.

Call Sequence Number

The unique sequence number for the web service is displayed here.

Calling Stage

Select the stage at which web service should be called from the drop-down list.

Status

The system defaults the status of the web service.

8.2.2 Web Service Details

Web Service details is attached to the maintenance screens for which web service call is required. You can invoke this screen by typing 'CSCEXWSM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

| WebService Code | Calling Sequence Number | Calling Stage | Status | Details |
|--------------------------|-------------------------|---------------|-------------|---------|
| <input type="checkbox"/> | | PRE | Unprocessed | Details |

WebService Code

Select the unique web service code from the adjoining option list.

Call Sequence Number

The system displays the unique sequence number for the web service.

Calling Stage

Select the stage in which the web service should be called from the drop down list.

Status

Select the status of the web service from the drop down list.

Note

- When any operation is done in the screen and call to back end is made, the request built during this process will have the information of web services to be called. The web service call will be made based on the status of each web service which will be updated in the backend.
 - The details of an external web service is taken from the maintenance screen based on the web service code mentioned in the call form. Each web service should be deployed in the URL mentioned in the maintenance before processing the request.
 - A flag will be set to find whether the request contains the web service information and the same will be used for parsing the request in the application server. Call to the web service is based on the request format that particular web service accepts. The request to the web service should be in that format and it can be written in the handler class provided.
-

Sending request to back end involves two cases:

- I If in the request, option to call the web service is pre, then the web service will be called and the response from the web service will be appended in the request before sending it to the back end.

- I If in the request, option to call the web service is post, then the request will sent to back end first and the response from the back end will be sent to the web service. The response from the web Service Call will be appended in the request and sent to the backend again.

8.2.3 WebService Maintenance

Web Service Maintenance is attached to the maintenance screens for which web service call is required. You can invoke this screen by typing 'CSDEXWSD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

| | |
|-------------------------|--|
| WebService Code | |
| Calling Sequence Number | |
| Calling Stage | |
| Status | |
| Key Id | |
| Request | |
| Response | |

WebService Code

The system displays the unique code of the web service

Call Sequence Number

The system displays the unique sequence number of the web service

Calling Stage

Select the stage in which the web service should be called.

Status

The system defaults the status of the web service.

Key ID

The system defaults the ID for which the web service is called.

Request

The system displays the request of the web service.

Response

The system displays the response of the web service.

9. Accounts for Inter-Branch Transactions

9.1 Defining Accounts for Inter-Branch Transactions

A transaction that takes place in a branch of your bank may involve accounts that are maintained in another branch. For example, a customer has an account in the Head Office branch and approaches another branch of the bank for a cash withdrawal.

For each combination of branches that may be involved in an inter-branch transaction, you can define the currency and the respective customer accounts to which the related accounting entries will be posted.

The accounting entries for such inter-branch transactions can be routed in one of the following ways:

- **Directly** - where each branch will have a direct accounting relationship with all other branches
- **Through a Regional Office** -- where two branches involved in a transaction will interact through a common RO
- **Through the Head Office** -- where the two branches involved in the inter-branch transaction will interact only through the HO.

This route for all transactions is defined in the 'Bank parameters' screen.

In the 'Inter-branch Parameters Maintenance' screen you define the internal accounts for pairs of branches that would be involved in any inter-branch accounting.

Invoke this screen by typing 'ACDIBMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

Inter Branch Accounts Maintenance

New Enter Query

Branch 1 *
Description
Branch 2 *
Description

General Ledger

Accounts
Due To Branch 2 *
Description
Due From Branch 2 *
Description
Inter Branch Currency * Account Currency

General Ledger

Accounts
Due To Branch 1 *
Description
Due From Branch 1 *
Description
Inter Branch Currency * Account Currency

Contingent General Ledger

Due To Branch 2 *
Description
Due From Branch 2 *
Description

Contingent General Ledger

Due To Branch 1 *
Description
Due From Branch 1 *
Description

MIS Group

Due to Branch 2
Description
Due from Branch 2
Description

MIS Group

Due to Branch 1
Description
Due from Branch 1
Description

Fields

Input By
Date Time

Authorized By
Date Time

Modification
Number
☐ Authorized
☐ Open

In this screen you maintain the following for each combination of branches that may be involved in an inter-branch transaction:


- Branch Code of both the branches that are involved in the transaction
- For each of the branches, whether inter-branch entries must be posted in transaction currency or settlement account currency
- Customer accounts of Branch 1
 - Due to Branch 2
 - Due from Branch 2
- Customer accounts of Branch 2
 - Due to Branch 1
 - Due from Branch 1

9.1.1 System Features

The system generates a set of pairs of branches for which internal accounts should be maintained. The pairs generated depend upon on two factors:

- The reporting structure for the branches as created in the 'Branch parameters' screen and
- The route defined for inter-branch transactions in the 'Bank-wide parameters -- Preferences' screen,

For example, the following represents the reporting structure of your bank:



If you have defined a direct inter-branch accounting route then you need to maintain an accounting relationship for each possible combination of

- Branch and branch
- Branch and RO
- RO and HO
- Branch and HO

For the above mentioned reporting structure the system will offer the following pairs of branch combinations to be maintained:

1. BR1- BR2
2. BR1- RO1
3. BR2- RO2
4. RO1- HO
5. RO2- HO
6. BR1 - RO2
7. BR2 - RO1
8. BR1 – HO
9. BR2 – HO
10. RO1 - RO2

If you have defined 'through RO' inter-branch accounting route then you need to maintain an accounting relationship for each possible combination of

- Branch and RO/HO
- RO and RO

In the branch and RO pair, the RO should be that RO to which this branch reports. For the above mentioned reporting structure the system will offer the following branch pairs to be maintained:

1. BR1 - RO1
2. BR2 - RO2
3. RO1 – HO
4. RO2 – HO
5. RO1 - RO2

If you have defined 'through HO' inter-branch accounting route then you need to maintain an accounting relationship for each possible combination of,

- Branches and HO

- ROs and HO

For the above mentioned reporting structure the system will offer the following branch pairs to be maintained:

1. HO - RO1
2. HO - RO2
3. HO - BR1
4. HO - BR2

The system has an in-built auto escalation path for inter-branch accounting transaction which escalates from Direct to Through RO to Through HO.

For example, in the 'Bank preferences' screen you have defined a 'direct' inter-branch accounting relationship. But in the 'Inter-branch Accounts' maintenance screen (where all inter-branch accounts are maintained), you have not maintained an accounting relationship between two branches -- 000 and 002. Then, in case of an inter-branch accounting transaction between 000 and 002, the system will first look for a 'direct relationship' since that has not been maintained it will look for a relationship through RO i.e., if the two branches have a common RO; if that too does not exist then 'through HO' the transaction would take place.

9.1.2 **Specifying Customer Accounts**

System determines the settlement route for inter-branch transactions by considering the customer accounts that you specify for a particular currency in this screen.

For example, your bank has to process a transaction in USD involving your branch (Branch Code 001) and another branch (Branch Code 002). If you maintain the customer accounts for the branch pair 001-002 and currency USD, system will accordingly determine the settlement route.

Branch1 and Branch2

To specify a branch pair for which you want to define the customer accounts, you can choose from a list of maintainable branch pairs displayed by the System. The description of Branch 1 and Branch 2 are displayed below the respective branch codes.

9.1.2.1 **Specifying General Ledger Details**

Specify the customer accounts which are involved in the inter-branch transaction, in the respective branches

To maintain customer accounts for the branch pair specified, the following parameters should be maintained:

Inter Bank Currency

For each branch, you have the option of specifying whether the inter-branch entries must be posted in the transaction currency or the settlement account currency.

For the booking branch, if the Inter-branch Transaction Currency option specified is Transaction Currency, inter-branch entries are posted in the transaction currency only if:

- The local currency of both branches involved in the transaction is the same
- One of the accounts in the entries belongs to the booking branch

Due To Branch 2

This field identifies the customer account maintained in Branch 1 into which the credit accounting entry is passed.

To specify the customer account, select the appropriate account from the picklist of all the customer accounts maintained at Branch 1 .

Due From Branch 2

This field identifies the customer account maintained in Branch 1 into which a debit entry will be passed.

Due to Branch 1

This identifies the customer account maintained at Branch 2 into which a credit entry will be passed.

Due From Branch 1

This account identifies the customer account maintained at Branch 2 into which a debit entry will be passed.

System uses the customer accounts specified in this screen and determines the settlement route for a transaction between two different branches of your bank.

9.2 Defining Accounts for Inter-Branch Fund Transactions

A fund transaction that takes place in a branch of your bank may involve accounts that are maintained in another branch.

As mentioned earlier, if you have selected the option 'Allow Corporate Access' in the Branch Parameters screen and the branch is a fund branch, the IB Entity will be defaulted as General Ledger. The GL that will be used will be based on the maintenance in the Fund Inter Branch Accounts Maintenance screen, for the fund id.

To invoke this screen, type 'IADIBMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Fund Inter Branch Parameters Detailed

New Enter Query

Branch 1 *
Description
Fund Id *

Branch 2 *
Description
☒ Fund Branch

General Ledger

Accounts
Due To Branch 2
Description
Due From Branch 2
Description
Trans Currency Branch 2 Account Currency

Accounts
Due To Branch 1
Description
Due From Branch 1
Description
Trans Currency Branch 1 Account Currency

MIS Group

Due To Branch 2
Description
Due From Branch 2
Description

Due To Branch 1
Description
Due From Branch 1
Description

Input By Date Time
Authorized By Date Time
Modification Number
☐ Authorized
☐ Open

For a fund id, specify all the details necessary to define the Inter branch GL that will be used. The option list against the field Fund ID includes all the valid funds maintained in the system.

For an explanation on each of the other fields, refer to the previous section.

9.2.1 Querying on Netting Batch

You can view all netted and non-netted transactions of the netting process from the 'Netting Batch Query' screen. You can invoke this screen by typing 'STDNETQY' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Netting Batch Query

New Enter Query

Group Code
Account Number
Date

Netting Batch Details

1 Of 1

| Netting Reference Number | Date | Branch | Account | Module |
|--------------------------|------|--------|---------|--------|
| | | | | |

Exit

You can query on the basis of one or more of the following parameters:

- Netting Group Code
- Account Number
- Date

On searching, the system displays the following details:

- Netting Reference Number
- Date
- Branch Code
- Account
- Module
- Event
- Reference Number
- Transaction Code
- Amount Tag
- Debit/Credit Transaction
- Account Currency
- Foreign Currency Amount
- Local Currency Amount

10. Currency Maintenance

10.1 Introduction

In the 'Currency Definition' screen, you define the attributes of the currencies in which your bank can deal. For each currency, you can define attributes like, the SWIFT code for the currency, the country to which the currency belongs, the interest method, the spot days, the settlement days, etc.

Currencies can be maintained only at the Head Office. The list of currencies will be made available to all the branches of your bank.

Invoke this screen by typing 'CYDCDEFE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

10.2 Maintaining Currency Details

Currency Code

Currencies are identified in Oracle FLEXCUBE by the SWIFT codes assigned to them. The currency will be identified by this code in all transactions that involve it.

Currency Name

You can enter the detailed name of the currency in not more than thirty-five alphanumeric characters.

Currency Type

As per your bank's requirement you can choose to classify currencies into different currency types. The bank can use its own discretion to decide the basis of classifying currencies into different currency types. A currency type can consist of a maximum of three characters.

Depending on the customer account mask maintained, the value in the currency type field would be used during the generation of customer account numbers through the Customer Accounts Maintenance screen.

If you have decided to include currency type as part of the customer account number (in the account number mask), then at the time of creating a new customer account number, you will need to select the currency of the account number being generated. In the option-list provided for currency, the currency code is displayed along with the associated currency type say, USD – 1, GBP – 2 etc. When the account number gets populated, it is the currency type that forms a part of the customer account number.

ISO Numeric Currency Code

Specify the currency code specified by the International Standardization Organization.

Country

After you have identified the currency, you should indicate the country to which the currency belongs. You can select a country code from the option list available.

Decimals

You can indicate the number of decimal units up to which the currency can be denominated. The number of decimals allowed for any amount in the currency can be:

0 - Currency with no decimals

2 - Currency with two decimals

3 - Currency with three decimals

Interest Method

You can indicate the interest rate to be used for transactions that involve this currency. The interest options available are:

- Actual/Actual
- 30(US)/360
- Actual/360
- 30(Euro)/365
- 30(US)/365
- Actual/365
- 30(Euro)/Actual
- 30(US)/Actual
- Actual/Actual

Select the interest method that should be used by default whenever the currency is used in transactions. While processing a transaction that involves this currency, the interest method defined for the currency is defaulted. You have the option to change it for a specific transaction.

However, if you do not specify an interest method for a transaction, the method defined for the currency will be used (For details refer to Annexure on Page 140).

Spot Days

The number of spot working days applicable for the currency is specified here. Payment advises for FX and MM contracts will be generated on a date, which is calculated as the number of spot working days before the Maturity Date of the contract.

For example, the tenor of an MM contract is as follows:

Value Date - 01/01/99

Maturity Date - 31/01/99

Contract Currency - USD

Contract Amount - 5000

For USD, the number of Spot Days is specified as: **Spot Days - 3**

For this contract, the payment advices will be sent on 28/01/96.

Foreign Exchange Netting Days

Oracle FLEXCUBE provides a facility wherein all transactions relating to a customer, meant to be settled on a particular day and are made before a specific cut off day are collated, netted and a single payment message is sent instead of individual messages for each payment. This cut off day can be parameterized and is called 'Netting Days'. The number of FX netting days applicable for the specified currency is maintained here.

Note

The system will validate that the FX Netting days are lesser than or equal to the spot days.

Settlement Days

In this screen, you can specify the 'Settlement Days' for a currency. Settlement messages for the components of a contract (in the LC, BC, LD, MM, FX, and FT modules) will be generated according to the settlement days specified for the currency of the settlement account. The following example illustrates this.

For example, when maintaining the details of USD in the Currency screen, you specify the 'Settlement Days' as '2'. This implies that two working days prior to the settlement of a component through a USD account, a settlement message will be automatically generated if specified (when you run the Settlement Messages function at the end of day).

The settlement details of a contract are as follows:

Settlement Date: 06 May 1999

Settlement Account Currency: USD

Component: Principal

Settlement Message: **Yes**

Component Currency: GBP

When you generate the Settlement Messages function, at the end of day, on 04 May 1999, a settlement message for the Principal component of the contract will be generated.

You can run Settlement Messages function as part of EOD operations from the Application Browser to automatically generate settlement messages for contracts marked out for automatic liquidation.

The settlement day specification for a currency will determine the contracts that are picked up for settlement message generation.

Cut-off Time

The Currency Cut-off time refers to the time by which all transactions involving a currency should be generated. For a currency, you can indicate the cut-off hour and minute. This time should be expressed in the local time of the bank.

The maintenance of a cut-off time for a currency has particular reference to outgoing funds transfers involving it.

Cut-off days

You can also specify the cut-off days and time for payment transactions involving the currency.

For example, the value date of a funds transfer transaction (incoming payment) involving USD, is 3rd June 2001. The number of cut-off days specified for the currency is 2. This means that the payment must be received on or before 1st June 2001. If the payment is received on 1st June, it must be received before the cut-off time specified for USD.

If the USD cut-off time is 1200 hrs, then, if the payment is received on 1st June 2001, it must be received before 1200 hrs.

The cut-off time (in hours and minutes) that you maintain to be applicable for payment transactions involving a currency are applicable to the head office branch of your bank.

If the branches are in time zones other than the head office branch time zone, you must maintain the offset time applicable for each branch, in the Branch Parameters screen.

Note

Even when cut-off days and cut-off time for a currency have both been specified, the cut-off checks are performed for a funds transfer transaction only if specified as applicable for the product involved in the transaction.

Position or Position Equivalent GL for a currency

If you have opted for position accounting in your bank, you should indicate the Position GL and the Position Equivalent GL, when maintaining a foreign currency, in the currency screen (the Currency Definition screen).

When maintaining the GLs in your bank, you can opt to link the different foreign currencies, associated with the GL to either of the following:

- The Position GLs that you specify here (for the corresponding currency)
- Position GLs of your choice

Tolerance Limit

When you are maintaining an 'In' Currency, or the Euro, in the Currency Definition screen, you can define a 'Tolerance Limit' for it. The limit is expressed as a percentage.

The implication:

During the transition period, settlement of components in 'In' currencies can be made either in the same currency or in the Euro (EUR) depending on the settlement account(s) maintained. (Similarly, components in Euro can either be settled in EUR or in an 'In' currency.) In the settlement messages that are generated (MT 100, MT202), the settlement amount would be reported in the Settlement Account Currency. However, you can opt to additionally furnish the value of the component in Euro Related Information (ERI) currency. You have to manually specify the settlement amount value, in the ERI currency, in the Settlement Message Details screen.

When generating the message towards settlement (MT100, MT202), the system ensures that the value you specify as the ERI Amount conforms to the Tolerance Limit defined for the ERI Currency (in the Currency Definition screen). That is, the system computes the ERI equivalent of the settling amount using the pegged rates, and compares the same against the ERI

amount input by the user. If the difference is within the tolerance limits defined for the ERI currency, the user specified amount is used.

If the user specified ERI amount breaches the Tolerance Limit defined for the ERI currency, the system calculates and reports the ERI Amount on the basis of the exchange rate defined for the settlement currency vis-à-vis the ERI currency.

For example, in the SWIFT messages (MT 100 and MT 202) that are generated towards settlement, the value of the component can be reported both in Nostro account currency (in Field 32A) and in an ERI currency that you specify (in Field 72). In Oracle FLEXCUBE, this information is captured in the European Related Information (ERI) fields in the Settlement Message Details screen.

Assume the following scenario:

- The settlement account is an EUR account
- You have to settle an amount of DEM 10000
- You have defined the ERI currency for DEM as DEM
- The Tolerance Limit for DEM as 0.05%
- The exchange rate: 1 Euro = 1.30 DEM

The settlement amount in Euro would therefore be 7692.36 (rounded to nearest higher cent). This amount will be reported in Field 32A of the settlement messages. Now, if you want to furnish the settlement amount in the ERI currency (in this case, DEM) you have to manually enter the DEM value in the ERI Amount field. You may enter DEM 10000. (EUR 7692.36 actually converts into DEM 10000.068.)

The value that you have entered is well within the Tolerance Limit of 0.05% defined for DEM. Therefore, this value will be reported in Field 72 of the settlement messages.

Since the Tolerance Limit for DEM is 0.05%, you can specify an ERI Amount between DEM 9995 and DEM 10005 ($\text{DEM } 10000 * 0.05/100 = \text{DEM } 5$). If you enter an ERI value exceeding DEM 10005 or less than DEM 9950, the system recalculates the ERI Amount at the time of generating the settlement messages. The recalculation will be on the basis of the pegged rates between the Settlement Currency and the ERI currency.

Note

The system validates the ERI amount only when generating the settlement messages. It does not validate the ERI amount at the time of input (in the Settlement Message Details screen).

Index Base Ccy

Specify the currency that should be used to handle index-based securities traded by the banks, wherein the deals are done in index currency and their settlement is done through the local currency.

Generate 103+

You can enable the MT 103 + format option only if you would like to generate outgoing MT 103 messages in the MT 103 + format.

If you are enabling this option for a specific currency, ensure to also enable this option:

- For your bank branch in the Branch Parameters Maintenance
- For the customer of the contract, in the BIC Code Maintenance
- For the product used by the contract, in the Product Preferences

Consequently, while processing transactions in the specified currency for such a customer, branch and product, for which the MT 103+ option is enabled, the system generates outgoing payment messages in the MT 103 + format.

Note

Since the system is also capable of processing incoming MT 103 messages in the MT 103 + format. Therefore, during the upload process for your branch, the system considers an MT 103 payment message to be of MT 103+ format for those customer, currency and product combinations, for which the MT 103+ option has been enabled.

CLS currency

To allow customers of your bank to settle their FX deals via the CLS (Continuous Linked Settlements) Bank, you can identify the currency to be a 'CLS Currency'. FX deals in the CLS currency only will be eligible to be routed through the CLS bank.

From the available list of CLS currencies, you can further maintain a list of 'allowed' or 'disallowed' currencies for a specific customer. Every customer who is a 'CLS Participant' will be allowed to trade in all the available CLS currencies unless specifically mentioned.

Refer the 'Continuous Linked Settlements' chapter of the Foreign Exchange User Manual for details on maintaining currency restrictions and other maintenances required for processing CLS deals in Oracle FLEXCUBE.

Index Flag

Check this box to derive index rate of the currency in Lending module.

Validate Tag 50F

Check this box to indicate that validations need to be performed for the 50F details captured for the ordering customer during contract input.

For more details on 50F validations, refer the chapter titled 'Maintaining Addresses for a Customer' in Messaging System user manual.

Note

Customer cover messages are always generated in new format (MT202COV or MT205-COV).

For more details on new cover message formats, refer settlements user manual.

10.2.1 Indicating Rounding Preferences

Rule

This refers to the method to be followed for rounding off fractional units of a currency. The rounding preferences available are:

- Truncate — The amount is truncated to the number of decimals specified for the currency
- Round Up — The amount is rounded up based on the number of decimals and the nearest rounding unit
- Round Down — The amount is rounded down based on the number of decimals and the nearest rounding unit

For example,

| Amount before Rounding | Rounding Method | No. of Decimals | Rounding Unit | Amount after Rounding |
|------------------------|-----------------------------------------|-----------------|---------------|-----------------------|
| 1234.678 | Truncate | 2 | - | 1234.67 |
| 1234.678 | Round up to the nearest rounding unit | 2 | .01 | 1234.68 |
| 1234.678 | Round down to the nearest rounding unit | 2 | .01 | 1234.67 |

Unit

If you have selected Round Up or Round Down in the Rule field, you need to indicate the nearest unit to which the rounding should take place. The number of units specified here should not be greater than the number of decimals allowed for the currency.

Example

The decimal points specified for currency 'A' is 2. Rounding unit is .05

Amount for transaction is USD 100.326, which will be rounded off depending upon the decimals specified and the rounding rule and rounding unit.

For Rounding Rule 'Up', the amount available for transaction would be USD 100.35. For rounding rule 'Down', the transaction amount would have been rounded down to 100.30

If the rounding rule was specified as 'truncate' then, the amount would have rounded off to 100.32 (simply, knock off all decimal points beyond the stated decimals places to be rounded off). Thus whenever you specify a 'truncate' option you need not state the 'Rounding unit'.

10.2.2 Specifying Amount Format Mask

Specify the format in which amounts in this currency are to be displayed for contracts in this currency. Two options are available:

999,999,999

9,999, 999, 99

The system defaults to the 999,999,999 format.

Euro Type

When maintaining a currency in the Currency Definition screen, you have to specify the 'type' of the currency with relation to transition phase of the European Economic and Monetary Union (EMU). You can do this in the 'Euro Type' field.

Your specifications in this field enable you to handle the *first phase* of the EMU, which commenced on 01 January 1999.

For more details on the manner in which Oracle FLEXCUBE handles the Euro, refer the chapter 'Handling the Euro'.

By choosing the appropriate option, you can indicate if the currency is:

- The Euro
- An 'In' currency
- An 'Out' currency

- 'Euro Closed'

National currencies of 'In' countries are referred to as 'In' currencies. When maintaining other currencies, you have to choose the 'Out Ccy' option under Euro Type.


When the transition period ends, the national currencies of the participating countries would cease to exist as valid legal tenders. The Euro would be the only legal tender in the participating countries. Consequently, the Euro changes made to Oracle FLEXCUBE will no longer be required.

You can turn off the changes at the end of the transition period by:

1. Closing all 'In' currencies, and
2. Choosing the 'Euro Closed' option (for the Euro)

10.2.3 **Specifying Exchange Rate Limits**

Click 'PC' button in the Currency Definition screen to invoke 'Limits' screen.



You can specify the credit limit and the debit limit for the exchange rate in this screen. The transaction amount of a PC contract must not exceed the limit specified here.

10.2.4 **Mapping Currency to Country**

Click 'Currency Country Mapping' button in the Currency Definition screen to invoke 'Clearing Zones Country Codes for Currency' screen.

The screen appears as shown below:

You can map a currency code to a country in this screen.

10.2.5 **Specifying User Defined Fields**

You can associate values to all the User Defined fields created and attached to the Currency Definition Screen. You can view the list of User Defined fields associated by clicking the 'Fields' button.

The screen appears as shown below:

You can enter the value for the UDFs listed here in the 'Value' column.

For more details on how to create user Defined fields, refer chapter 'Creating custom fields in Oracle FLEXCUBE' in the User Defined Fields User Manual under Modularity.

10.2.6 **Annexure**

The treatment for interest calculation varies with each of the interest calculation methods. Each method is dealt with individually below:

Actual/Actual Method

$$10,000 \times 10 / 100 \times (31/365 + 84/366)$$

In this method, the number of days is calculated as follows:

Dec. -31 days (include from date exclude to date)

Jan -31 days

Feb.-29 days (leap year)

March - 24 days (include from date exclude to date)

$$\text{Total} = 31 + (31+29+24=84) = 115$$

Note

When the interest period crosses from a non-leap year to a leap year (or otherwise), the basis of actual days has to be treated separately in each year.

Therefore, the denominator for the 31 days in December is 365 as it is a non-leap year and the denominator for the 84 days in 2000 is 366 as it is a leap year.

Actual /365 Method

$$10,000 \times 10 / 100 \times 115 / 365$$

In this method, the number of days is calculated as follows:

Dec. -31 days (include from date exclude to date)

Jan -31 days

Feb.-29 days (leap year)

March - 24 days (include from date exclude to date)

$$\text{Total} = 31 + 31 + 29 + 24 = 115$$

Actual/360 Method

$$10,000 \times 10 / 100 \times 115 / 360$$

In this method, the number of days is calculated as follows:

Dec. -31 days (include from date exclude to date)

Jan -31 days

Feb.-29 days (leap year)

March - 24 days (include from date exclude to date)

$$\text{Total} = 31 + 31 + 29 + 24 = 115$$

30 Euro/Actual Method

$$10,000 \times 10 / 100 \times (30/365 + 84/366)$$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 Euro Method, all months have 30 days, February included.)

Feb. - 30 days (In 30 Euro Method, February always has 30 days, leap year or not)

March - 24 days (include from date exclude to date)

Total = 113 days

Note

When the interest period crosses from a non-leap year to a leap year (or otherwise), the basis of actual days has to be treated separately in each year.

30 Euro/365 Method

$10,000 \times 10 / 100 \times 114 / 365$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 Euro Method, all months have 30 days, February included.)

Feb. - 30 days (In 30 Euro Method, February always has 30 days, leap year or not)

March - 24 days (include from date exclude to date)

Total = 113 days

30 Euro/360 Method

$10,000 \times 10 / 100 \times 114 / 360$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 Euro Method, all months have 30 days, February included.)

Feb. - 30 days (In 30 Euro Method, February always has 30 days, leap year or not)

March - 24 days (include from date exclude to date)

Total = 113 days

30 US/Actual Method

$10,000 \times 10 / 100 \times (30 / 365 + 84 / 366)$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 US Method, all months have 30 days, only for February are the actual number of days calculated.)

Feb. - 29 days (In 30 US Method, actual days are accounted for the leap year.)

March - 24 days (include from date exclude to date)

Total = 113 days

Note

When the interest period crosses from a non-leap year to a leap year (or otherwise), the basis of actual days has to be treated separately in each year.

30US/365 Method

$10,000 \times 10 / 100 \times 114 / 365$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 US Method, all months have 30 days, only for February are the actual number of days calculated.)

Feb. - 29 days (In 30 US Method, actual days are accounted for the leap year.)

March - 24 days (include from date exclude to date)

Total = 113 days

30US/360 Method

$10,000 \times 10 / 100 \times 114 / 360$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 US Method, all months have 30 days, only for February are the actual number of days calculated.)

Feb. - 29 days (In 30 US Method, actual days are accounted for the leap year.)

March - 24 days (include from date exclude to date)

Total = 113 days

10.2.7 Specifying Currency Cut-Off Parameters

You can choose to restrict the time within which (or before which) funds transfer transactions involving a specific customer, product, and a currency, must be received for processing. For a specific customer, product, and a currency, you can specify a certain number of days before which a transaction involving the combination must be received, as well as a cut-off time before which transactions must be received. These parameters are known as currency cut-off parameters, and you maintain these parameters in the 'Value Dated Spread' maintenance screen.

Invoke this screen by typing 'FTDVDSPP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

| Value Dated Spread Maintenance | | | | | |
|--------------------------------|--|----------------------|-----------------|------|--|
| New Enter Query | | | | | |
| Customer No * | | Currency Code * | | | |
| Customer Name | | Currency Description | | | |
| Product Code * | | | | | |
| Product Description | | | | | |
| Spread Details | | | Cut Off Details | | |
| Debit Value Date Spread * | | Days | | | |
| Credit Value Date Spread * | | Hour | | | |
| | | Minutes | | | |
| Fields | | | | | |
| Maker | | Date Time: | | | |
| Checker | | Date Time: | | | |
| Mod No | | Record Status | | | |
| | | Authorization Status | | | |
| | | | | Exit | |

In this screen, you can maintain the cut-off time, cut-off days and the value spreads to be applicable for:

- Each customer, for a product and currency combination
- All customers, for each product and currency combination

These currency cut-off parameters are validated in respect of a funds transfer transaction only if currency cut-off checks are specified as applicable in the product preferences, for the product involving the transaction.

For details about how the currency cut-off checks are applied on a funds transfer transaction, refer the chapter 'Processing a Funds Transfer Contract' in the Funds Transfer User Manual.

10.3 Maintaining Currency Position Details

You can view the currency position through Currency Position Details screen. To invoke this screen type 'CYDCCYLS' in the field at the top right corner and click the adjoining arrow button in the application toolbar.

The screenshot shows the 'Currency Position Details' application window. At the top, there's a title bar and a toolbar with an 'Execute Query' button. Below the toolbar, a 'Branch Code' field is set to '001'. The main area is titled 'Currencies Current Position' and contains a table with the following columns: 'Currency' (with a dropdown arrow), 'Cash Position', 'Spot Position', 'Forward Position', 'Open Position', 'Accrual Position', and 'Global Position'. The table is currently empty. Below the table, there are four buttons: 'Spot Position', 'Accrual Position', 'Change Position', and 'Forward Position'. A 'Cancel' button is positioned at the bottom right of the window.

In this screen, system calculates and displays the currency positions for different currencies.

You can view the following positions of each currency in a selected branch:

- **Cash Position** - This gives the currency wise cash position based on the transactions booked across all the modules in Oracle FLEXCUBE. It considers the entries that are formed under Asset, Liability, Income and Expenses GL heads for which 'Report as Accrual' at GL Maintenance screen is not checked.
- **Spot Position** - This position is derived based on the outstanding deals from various modules for which the maturity date falls on the spot days as maintained in the 'Currency Maintenance' screen.
- **Forward Position** - This position is acquired based on the outstanding deals from various modules for which the maturity date falls after the spot days maintained in the 'Currency Maintenance' screen.
- **Open Position** - This position is a combination of Cash Position, Spot Position and Forward Position
- **Accrual Position** - This gives the currency wise position across all the modules in Oracle FLEXCUBE considering the entries that formed under Asset, Liability, Income and Expenses GL heads for which 'Report as Accrual' at 'GL Maintenance' screen is checked.
- **Global Position** - This position is a combination of Cash Position, Spot Position, Forward Position and Accrual Position.

Note

Check 'Report as Accrual' field in 'GL Chart of Accounts Maintenance' screen to calculate the accrual entries posted to this GL. This is displayed during the online query of FX positions. Depending on your selection in this field, system will arrive at the cash and accrual positions.

Click 'Spot Position' to view the details of the deals that have contributed to spot position.

Spot Position Details

Print Enter Query

Currency Code * GBP

Spot Position Details

| Reference Number | Client Description | Debit/Credit | Amount | Value Date | Exchange Rate | Against Currency |
|------------------|--------------------|--------------|--------|------------|---------------|------------------|
|------------------|--------------------|--------------|--------|------------|---------------|------------------|

Exit

Click 'Change Position' to view the details of the deals that have contributed to change position.

Currency Change Position

Execute Query

Branch * 001

Currency * EUR

Cash Position

Cash Position

| Reference Number | Customer Description | Debit/Credit | Amount | Value Date | Exchange Rate | Against Currency |
|------------------|----------------------|--------------|--------|------------|---------------|------------------|
|------------------|----------------------|--------------|--------|------------|---------------|------------------|

Exit

Click 'Accrual Position' to view the details of the deals that have contributed to accrual position.

Click 'Forward Position' to view the details of the deals that have contributed to forward position.

10.4 Handling Euro

On 1 January 1999, eleven countries that are part of the European Union embarked on the first phase of economic integration, called the 'Economic and Monetary Union' (EMU). In Oracle FLEXCUBE, the eleven countries participating in the first phase of the EMU are referred to as 'In' countries and the respective national currencies as 'In' currencies. All other countries are referred to as 'Out' countries.

The first phase of the EMU, referred to as the 'transition period', ushered in a new, single European currency: the **Euro (EUR)**. During this phase, the National Currency Denominations of 'In' countries would co-exist with the Euro. That is, transactions involving an 'In' currency would, typically, be routed through the Euro during this phase. At the end of the transition period, in mid 2002, however, the national currencies of the participating

countries would cease to exist as valid legal tenders. The Euro would be the only legal tender in 'In' countries.

In Oracle FLEXCUBE, you can handle the Euro and the attendant implications for your bank, by capturing additional currency and settlements related information. This chapter details how this information is to be captured, and its implications.

10.5 Maintaining Euro Related Information

In Oracle FLEXCUBE, the details that you need to maintain in order to handle the EMU include:

- Maintaining Euro as a valid currency
- Indicating if a currency is 'In', 'Out', 'Euro', or 'Euro Closed'
- Maintaining Currency Redenomination details
- A common conversion GL and a transaction code to identify the redenomination entry
- Maintaining a 'Tolerance Limit' for a currency (to check against ERI information)
- Capturing additional settlement details (Euro related information for the MT 100 and MT 202 SWIFT messages)

You can maintain currency related information in the Currency and the Currency Pair Definition screens. 'Settlement' details can be captured in the Settlement Instruction Details screen.

10.5.1 Maintaining Currency Details

Your specifications for a currency in the Currency Definition screen determine the manner in which transactions in the currency are handled in Oracle FLEXCUBE.

Currency Type

When maintaining a currency in the Currency Definition screen, you have to specify the 'type' of the currency. You can do this in the 'Euro Type' field. Choose the appropriate option from the following:

- The Euro itself
- An 'In' currency
- An 'Out' currency
- 'Euro Closed'

National currencies of 'In' countries are referred to as 'In' currencies. When maintaining other currencies, you have to choose the 'Out Ccy' option under Euro Type.

When the transition period ends, the national currencies of the participating countries would cease to exist as valid legal tenders. The Euro would be the only legal tender in the participating countries. Consequently, the Euro changes made to Oracle FLEXCUBE will no longer be required.

You can turn off the changes at the end of the transition period by:

- Closing all 'In' currencies, and

- Choosing the 'Euro Closed' option (for the Euro)

Tolerance Limit

When you are maintaining an 'In' Currency, or the Euro, in the Currency Definition screen, you can define a 'Tolerance Limit' for it. The limit is expressed as a percentage.

The Implication:

During the transition period, settlements of components in 'In' currencies can be made either in the same currency or in the Euro (EUR) depending on the settlement account(s) maintained. (Similarly, components in Euro can either be settled in EUR or in an 'In' currency.) In the settlement messages that are generated (MT 100, MT202), the settlement amount would be reported in the Settlement Account Currency. However, you can opt to additionally furnish the value of the component in Euro Related Information (ERI) currency. You have to manually specify the settlement amount value, in the ERI currency, in the Settlement Message Details screen.

When generating the message towards settlement (MT100, MT202), the system ensures that the value you specify as the ERI Amount conforms to the Tolerance Limit defined for the ERI Currency (in the Currency Definition screen). That is, the system computes the ERI equivalent of the settling amount using the pegged rates, and compares the same against the ERI amount input by the user. If the difference is within the tolerance limits defined for the ERI currency, the user specified amount is used.

If the user specified ERI amount breaches the Tolerance Limit defined for the ERI currency, the system calculates and reports the ERI Amount on the basis of the exchange rate defined for the settlement currency vis-à-vis the ERI currency.

The following example illustrates the application of the Tolerance Limit.

Note

The system validates the ERI amount only when generating the settlement messages. It does not validate the ERI amount at the time of input (in the Settlement Message Details screen).

Currency pairs

In the Currency Pair Definition screen, you can specify a 'Through Currency'. When maintaining a pair involving an 'In' currency ('In' – 'Out' and 'In' – 'In'), you can only specify the Euro as the 'Through Currency'.

Note

You cannot maintain a 'Through Currency' for a pair constituted by an 'In' currency and the Euro.

10.5.2 Maintaining Conversion GLs

To facilitate the currency conversion process, two additional parameters need to be maintained in the 'Branch Parameters' screen. You have to maintain a common Conversion GL and a Transaction Code that identifies redenomination entries.

The screen is as shown below:

10.5.2.1 Indicating Euro Redenomination General Ledger

Conversion GL

The conversion GL that you specify will be identified as the common Suspense GL for all balance conversions while re-denominating the currency of an account either for specific customers or for generic conversions.

Transaction Code

In addition to the conversion GL, you have to indicate a Transaction Code, which identifies conversion related entries.

10.5.3 Implications of Currency Redenomination

In the IC Product Accounting Role Definition screen

For the purpose of currency conversion, an accounting role called 'Acquired' is available.

End of day processes

Maintaining a Conversion GL and Transaction Code simplifies the End of day process. Basically two important things happen when the End of day processes are run. Firstly interest is liquidated to the Acquired Interest GL and secondly all balances will be reduced to zero.

When you run the Beginning of day processes the next day the change in the currency conversion will be in place. In addition balances will get restored.

Change in field values due to conversion

The change in currency re-denomination impacts amount based fields pertaining to Accounts, Collaterals, Credit Lines and Customer Limits. The change in the value of these fields is reflected when you run the beginning of day processes.

The amount-based fields, which are affected by the change in currency denomination, will be updated with the equivalent value in the new currency

Accounts

The following fields will reflect the new values:

- Temporary Over Draft limit
- Sub-limit
- Uncollected Funds limit
- Offline limit
- Account Currency

These fields can be found in the Customer Accounts Maintenance screen.

Collateral

In the Limits Maintenance Collaterals screen the following fields will be updated:

- Collateral Currency
- Collateral Value
- Limit Contribution
- Issuer Exposure Amount

Credit Lines

In the Limits screen of the Limits Maintenance module the following fields will reflect the new values:

- Credit Line Currency
- Tenor limits
- Tenor utilization
- All Related Amounts

Customer Limits

In the Customer Maintenance screen of the Core Services module the following fields will be updated at BOD.

- Limit Currency
- Liability Risk Limit
- Customer Risk Limit

Note

Once the conversion process is complete the advices generated for your customer will carry the following information:

- The Old Value
- The New Value
- And the Exchange Rate used for the conversion

As a consequence of currency re-denomination you will not be able to pass entries where the value date falls before the currency conversion date.

10.5.4 Specifying Preferred ERI Currency for Counterparty

For a counterparty and currency (combination), you can maintain a preferred ERI currency. You can state this preference in the 'Settlement Instructions' screen.

The Implication

During the transition period, settlements of components in 'In' currencies can be made either in the same currency or in the Euro (EUR) depending on the settlement account(s) maintained. (Similarly, components in Euro can either be settled in EUR or in an 'In' currency.) In the settlement messages that are generated (MT 100, MT202), the settlement amount would be reported in the Settlement Account Currency. However, you can opt to additionally furnish the value of the component in Euro Related Information (ERI) currency. You can maintain this ERI currency (for a counterparty and currency combination) in the 'Settlement Instructions Maintenance' screen.

In the SWIFT messages that are generated towards settlement of a component (involving the counterparty and the currency), the component value will be expressed in this (ERI) currency, by default. Invoke this screen by typing 'ISDINSTN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot shows the 'Settlement Instructions Maintenance' window. It features a top bar with 'New' and 'Enter Query' buttons. The main area is divided into several sections for data entry:

- Counterparty:** Fields for Counterparty Name, Counterparty (with a CIF dropdown), Currency, and Branch.
- Module:** Fields for Module, Product Code, Sequence Number (with a value of 0), and Relations.
- Pay/Receive:** Two columns of fields for Branch, Currency, Account, Description, and Payment By.
- Cover:** A checkbox for 'Cover Required', a 'Cover By' dropdown, and radio buttons for 'Charges Details' (Ourselves, Beneficiary, Shared).
- Intermediary:** Two columns of fields for Intermediary Reimbursement Institution, Intermediary, and Country.
- RTGS:** A checkbox for 'Rtgs Payment' and a field for 'RTGS Network'.

At the bottom, there is a 'Fields' section with labels for Maker, Checker, Date Time, Mod No, Record Status, and Authorization Status, along with an 'Exit' button.

10.5.5 Specifying Settlement Message Details

SWIFT messages (MT 100/MT202) generated towards settlement can furnish the value of the settlement amount in both the settlement account currency, and an 'ERI' currency. If you opt to furnish the ERI value of the amount, you have to enter the following in the 'Settlement Details' screen:

- The ERI currency
- The ERI Amount

The screen appears as shown below on clicking 'Settlements' button in the contract screen:

Settlement Details

Reference Number * Component

Account Details Message Details Parties Parties Cover Parties Other Details Clearing Details Local Clearing

IBAN Account Number

Settlement Details

| Component | Currency | Branch | Account | Account Currency | Dr/Cr | Original Exchange Rate | Exchange Rate | Rate Code |
|----------------------|----------------------|----------------------|----------------------|----------------------|----------------------|------------------------|----------------------|----------------------|
| <input type="text"/> | <input type="text"/> | <input type="text"/> | <input type="text"/> | <input type="text"/> | <input type="text"/> | <input type="text"/> | <input type="text"/> | <input type="text"/> |

Settlement Direction Component Description

D - Debit
C - Credit

Signature Verification

The system defaults to the ERI currency specified for the customer and currency combination. You can change the default ERI currency. The ERI amount that you specify will be validated against the Tolerance Limit specified for the ERI currency.

10.5.6 Settlements of Foreign Exchange Deals

Oracle FLEXCUBE allows cross currency settlements of foreign exchange deals that involve an 'In' currency. You can settle the 'In' currency leg in another 'In' currency or in 'Euro'.

10.5.7 Reports and Advices

The following reports furnish the equivalent Euro values of amounts in an 'In' currency. The 'locked in' exchange rates defined for the Euro against the 'In' currency will be used for currency conversions.

The reports with this feature are the:

- Currency Position report
- Cash Flow report
- FX Maturity report

Note

These reports will not furnish the 'In' currency and equivalent Euro values when you close the 'In' currencies, and choose the 'Euro Closed' option (for the Euro) in the Currency Definition screen.

All advices that provide 'In' currency details will also provide the equivalent Euro values

Account Statements

Statements provided for accounts in an 'In' currency provide the Euro equivalent values of the following:

- The opening balance
- The closing balance
- Every transaction

10.5.8 Maintaining Limits Type

You can maintain various limit types and their values through the 'Limits Types Maintenance' screen. For example, you can define and maintain various Limit types like price codes, collateral types and price through this screen.

You can invoke this screen by typing 'LMDTYPES' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot shows the 'Types' maintenance screen. It includes a title bar, a toolbar with 'New' and 'Enter Query' buttons, and a main area with 'Type *' and 'Description' fields. Below these is a 'Values' section with a table. The table has two columns: 'Value' and 'Code'. The 'Value' column has a text field with a help icon. The 'Code' column has a text field. At the bottom of the window is a 'Fields' section with a blue background, containing labels for 'Input By Date Time', 'Authorized By Date Time', and 'Modification Number'. Below these are checkboxes for 'Authorized' and 'Open'.

Type

Specify the limit type for which you want to maintain values

Description

Specify the description for the limit type you are maintaining

Values

The values for the limit type that you are maintaining can be listed here. To add a value to the list of values, click on the 'Add' icon, and type the value. To remove a value from the list of values, check the box against that value and click on the 'Delete' icon.

Value

Specify the list of supported values. For example, MAIL, COURIER, BRANCH and so on.

Code

Specify the codes for the list of value. For example, CO, ML and so on.

10.5.9 Maintaining Transaction Limits

This section explains in detail about maintaining transaction limits, level of authorisations required for the transaction amounts and minimum user authorisation limit required for a transaction.

Oracle FLEXCUBE offers you a facility, whereby, each time a particular transaction processed in the system exceeds a certain limit; an override will be generated by the system.

You can maintain transactional limits for a module and product combination through the 'Product Transactional Limits Maintenance' screen. Invoke this screen by typing 'CSDPLMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

Product Transaction Limits Maintenance

New Enter Query

Module Identification * Source Code *

Module Description Transaction Limit Currency *

Product Code * Customer Type * All

Product Description

Product Transaction Limit Details

1 Of 1 Go

| Transaction Limit * | Level of Authorization | Minimum Authorization Limit | Cumulative |
|---------------------|------------------------|-----------------------------|------------|
| | | | |

Fields

Maker Date Time:

Checker Date Time:

Mod No Record Status Authorization Status

Exit

Module Identification

Each module in Oracle FLEXCUBE is identified by a code. First, you have to identify the module for which the currency-wise transactional limit is to be maintained. A list of all the modules operational at your bank will be displayed in the option list. You can choose the appropriate module code.

Module Description

The description associated with the module will be defaulted in the adjacent field.

Product Code

Each module contains a number of products within it. After you identify the module, indicate the product within the module for which you would like to maintain a currency-wise transactional limit. You can select the appropriate product code from the option list.

In the Product Transactional Limits screen, you can maintain the limits for:

- A specific module and a specific product
- A specific module and all products (select 'ZALL' as the Product Code)
- All modules (Select 'AL' as the Module Code) and all products

Product Description

The description associated with the module will be defaulted in the adjacent field.

Source Code

Specify the source code based on which you need to maintain the product transactional limits. The adjoining option list displays all valid source codes. The transaction limit amount maintained for the selected source code is used to validate transaction limit while authorizing the contract.

If the source code is available in Oracle FLEXCUBE, then the system enables all the fields available under 'Product Transaction Limit Details' multi grid.

If the source code external, then the system enables only 'Transaction Limit' available under 'Product Transaction Limit Details' multi grid.

Note

You cannot select a source code more than once.

Transaction Limit Currency

The transaction limit currency is the currency in which you would like to maintain the amount limit.

Customer Type

Select the type of customer for whom you are maintaining the transaction limits from the adjoining drop-down list. The following are the options available:

- Corporate
- Individual
- Bank
- All

10.5.9.1 Specifying Product Transaction Limit Details

Specify the following transaction limit details:

Transaction Limit

Specify a transaction limit. Each time you process a transaction, the system checks the transaction amount involved in the contract against the limit specified here. If the contract currency is different from the transaction limit currency, then the system converts the contract amount using the standard mid rate to the transaction limit currency and check against the transaction limit amount maintained for the product

The system displays an appropriate message indicating the levels of authorization if the transaction amount booked is in excess of the maintained transaction limit.

Level Of Authorization

Specify the number of authorisers to be involved in the authorising a particular transaction amount.

Note

The level of authorization should be greater than one.

Minimum Authorization Limit

This option is enabled only if the 'Cumulative' option is checked. Specify the minimum authorization limit required for a transaction. The authorization limit cannot be greater than the transaction limit. This amount is used to validate authorizer limit while authorizing the contract.

Cumulative

Check this option to indicate that multiple authorisers are allowed to authorise a transaction. The authorisers must have equal or greater than the minimum authorization limit maintained in this screen. The system displays an appropriate error message if the authoriser tries to authorise a transaction having transaction amount greater than the minimum authorising limit.

10.5.9.2 Validating Transaction Amount during Contract Processing

While saving a contract, the system will check the transaction amount against the cut-off amount maintained for the module and product currency involved in the transaction. If both the transaction currency and the limits currency are same, the comparison will be done directly. If different currencies are involved, the system will first convert the transaction amount into the cutoff amount currency using the STANDARD mid rate and then perform the validations.

To perform the check, the System will look for the limits maintained, in the following order:

3. The System looks for the limits maintained for a specific module and specific product combination
4. If the first option is not available, it checks the limits maintained for a specific module + ZALP (all products) combination
5. It checks the maintenance for AL (all modules) + ZALP (all products) combination

If the third option is also not available, the system displays an error message

When a transaction exceeds the amount limit, the system displays an override message while saving the transaction

10.6 Maintaining Sequence Generation Format

Every contract in Oracle FLEXCUBE is identified by a unique Contract Reference Number that is generated internally by the system. You are not allowed to modify this number. In addition, a contract is also identified by a unique User Reference Number. By default, the Contract Reference Number will be taken as the User Reference Number. But you have the option to change the User Ref Number.

Oracle FLEXCUBE also provides you the facility to generate the user reference number in a specific format.

To maintain a specific format, you need to identify the various components that would be part of the user reference number including details such as the length, order, value etc. of each component.

You can maintain a unique format through the 'Sequence Generation Input' screen. You can invoke this screen by typing 'CSDSEQGN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

You can maintain the following details of the sequence format:

Sequence Code

Each sequence format is identified by a unique sequence code. You can devise a code comprising a maximum of 20 alphanumeric characters.

Branch Code and Module Code

You can maintain the format for a specific branch and module combination. Select the branch code and the module code from the option-list. All authorized and active records will be displayed in the list.

Alternatively, you can maintain a sequence format that will be applicable to all the branches (ALL) and all the modules (AL) available in your bank.

Reset Frequency

You need to specify the frequency at which the system will drop and recreate the sequence numbers once again. At the reset frequency that you specify, all sequence numbers of the sequence format will be dropped and recreated again during the End of Day processing.

The options available are:

- None
- Daily

- Monthly
- Yearly

For example, let us assume that the running number in the sequence format is 4 characters long (starting from 0001) and the reset frequency is Monthly. Further, let us assume that the sequence number of the last contract processed on the last day of the month is 0199. At EOD of the last day of the month, the sequence numbers generated till date will be dropped and the system will begin regeneration starting from 0001 once again for all subsequent contracts.

Range

You can specify a range of sequential reference numbers. If you specify such a range, then no additional details need be specified. If you do not specify a range, you can specify additional details specific to each component of the sequence format.

In addition to the above details, you should also maintain details specific to each component of the sequence format. The details are as follows:

Component Order

Each component is assigned an order number based on which they would appear in the user reference number. The component order is automatically generated by the system and is non-editable.

Component

Each component in the sequence format is identified as one of the following:

- An Oracle FLEXCUBE Component – If your sequence format uses an Oracle FLEXCUBE column directly, you can specify it as an Oracle FLEXCUBE Component. For instance, you may want to include the product group associated with the product code involved in a contract, as a component in sequence number generation. To achieve this, you will use the Oracle FLEXCUBE column `PRODUCT_GROUP` (available in the table `CSTM_PRODUCT`) as an Oracle FLEXCUBE Component.
- A User Component – You may want the first two characters of your bank's name to be part of all the user reference numbers generated at your bank. You can define it as a user component. In addition, if you want to use the manipulated value of an Oracle FLEXCUBE Column in the sequence format, you can specify it as a User Component. For eg, you may want to include ONLY the first four characters of the product group in the sequence number. In this case, the component would be defined as a User Component.
- A Separator – To separate the various components from one another, you can use the component known as the separator. Eg: a back slash, a hyphen etc.
- A Running Number – Each contract is identified by a unique sequence number. It is mandatory to maintain a running number as a component in the sequence format. If not included, you will not be allowed to save the details of the format. A running number is internally generated by the system.

Component Type

You need to identify the type of each component in the sequence format. A component can be constant through out or change for every contract processed at your bank. You can associate a component with one of the following types:

- Static – To include any hard coded component in the sequence format, you will specify the type to be static. For instance, you may want the first two characters of your bank's name to be part of all the user reference numbers generated at your bank. The component type would be static in this case.
- Dynamic – You will specify the component to be of the dynamic type if its value is picked up from the Oracle FLEXCUBE table. Eg: Product Group. A running number would always be dynamic in nature.

Use in Sequence Generation

You need to indicate whether the component being defined should be used in sequence generation or not. Specify 'YES' or 'NO' as per your choice.

You can also choose to display the reference number in the advices that are generated for a contract.

Component Length

You can also specify the length of each component in the sequence format. The component value is dependent on the component length maintained. For instance, if you specify 2 as the component length, the value should comprise of only two characters.

Component Value

As stated earlier, the component value is dependent on the component length. Based on the length, you can specify a value comprising of as many characters as specified in the Component Length field. However, this field is used only if the value of the component is required to be constant (static type) in all the user reference numbers generated at your bank. If the component value is changing constantly (Dynamic type) for every contract, the system will automatically pick up the value from the DB table based on the SQL query that you maintain for the purpose.

Component Column and Component Table

If your component is of the dynamic type, you will need to mention the name of the Oracle FLEXCUBE column from where the system will pick up the component value. Further, if you wish to include a manipulated column value in sequence generation, you will need to include 'SUBSTR' as well in the column name. For eg, to include only the first four characters of the product group associated with the product code involved in a contract, you will specify the following in the Component Column field:

SUBSTR (PRODUCT_GROUP, 1, 4)

You need to mention the table name also, if the component type is dynamic. The following table names are available in the option-list provided.

- DUAL
- STTM_BANK
- STTM_BRANCH
- CSTM_PRODUCT

For our example, the table name would be CSTM_PRODUCT.

Component Where Clause

The condition or the 'where clause' of the SQL code is specified here. In the example discussed above, the system will pick up the appropriate product group depending on the product code involved in the contract being processed. You can specify the following where clause as an extension of the SQL statement specified earlier:

WHERE PRODUCT_CODE = SUBSTR (P_CRN, 4, 4);

Click add icon to define each subsequent component in the format. Use the navigating icons to move between the various components of a sequence format.

11. Maintaining Currency Denomination

11.1 Introduction

In the Data Entry module, you can specify a break up of a transaction amount for Teller transactions by denomination. The system also maintains a break-up of the till balances by denomination.

11.2 Maintaining Currency Denomination Details

In the 'Currency Denomination' screen, you maintain the standard currency denominations for each currency that your bank deals with. You can invoke this screen by typing 'CSDDEMAN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Denomination Details

New Enter Query

Denomination Type * Cash

Currency Code *

Currency Description

Issuer Code *

Issuer Description

Denomination Details

1 Of 1

| Denomination Id * | Denomination Description | Denomination Value * | Sequence Number | Type * |
|-------------------|--------------------------|----------------------|-----------------|--------|
| | | | | Note |

Maker

Checker

Mod No

Date Time:

Date Time:

Record Status

Authorization Status

Exit

To maintain the denominations of a currency, you need to specify the following:

- The code of the currency for which you are defining denominations
- A unique code to identify each denomination of the currency. For example, you can assign D1, D10, D50 for USD 1, 10, 50.
- A description of the denomination unit
- The denomination type coin or note
-
- The value of the denomination in relation to one unit of the currency. It could be a fraction for coins

For example, for the currency USD you can maintain the denominations as follows:

| CURRENCY CODE | DENM CODE | DESCRIPTIO N | VALU E | NOTE / COIN |
|---------------|-----------|--------------|--------|-------------|
|---------------|-----------|--------------|--------|-------------|

| | | | | |
|-----|------|---------------|--------|------|
| USD | D100 | 100 dollars | 100.00 | NOTE |
| USD | D50 | 50 dollars | 50.00 | NOTE |
| USD | D20 | 20 dollars | 20.00 | NOTE |
| USD | D10 | 10 dollars | 10.00 | NOTE |
| USD | D5 | 5 dollars | 5.00 | NOTE |
| USD | D1N | 1 dollar Note | 1.00 | NOTE |
| USD | D1C | 1 dollar Coin | 1.00 | COIN |
| USD | C25 | 25 cents | 0.25 | COIN |
| USD | C10 | 10 cents | 0.10 | COIN |
| USD | C5 | 5 cents | 0.05 | COIN |
| USD | C1 | 1 cent | 0.01 | COIN |

Denomination type Millionaire certificate is used to facilitate MC/LMC (Millionaire Certificate) transactions. You can have only one denomination with denomination type as 'Notes' and the currency code should be the LCY code of each country..

11.2.0.1 Operations Allowed in the Currency Denomination Screen

Following standard maintenance operations are possible in the 'Currency Denomination' screen:

- Add
- Modify
- Delete
- Authorize
- Close
- Re-open
- Inquiry
- Logs all maintenances in the Audit Trail.

12. Expressing Amounts in Words

12.1 Introduction

You can describe the amounts printed on account statements, messages, advices, etc., in words, for the benefit of your customers. To describe 'amounts' in a specific language, you have to maintain the verbal equivalents of numerals in the language. You can maintain verbal equivalents of numerals in the 'Amount Text Maintenance' screen.

You can invoke this screen by typing 'STDAMTRN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Amount Text Maintenance

New Enter Query

Language* Description

Text

| Amount* | Description | Prefix One |
|---------|-------------|-------------------------------------|
| | | <input checked="" type="checkbox"/> |

Currencies

| Currency* | Pre Decimal | Post Decimal | Final Text | Text Before | Fractions |
|-----------|-------------|--------------|------------|-------------------------------------|--------------------------|
| | | | | <input checked="" type="checkbox"/> | <input type="checkbox"/> |

Fields

Input By Date Time Authorized By Date Time Modification Number

☐ Authorized ☐ Open

Amount translation details can be maintained as one time maintenance at the time Oracle FLEXCUBE is installed at your bank. Once maintained, the amount descriptions printed on account statements, and other messages, will be described according to your specifications in this screen.

Language

You can maintain verbal equivalents of numerals in any language that Oracle FLEXCUBE supports. This means that you can maintain the verbal equivalents of numerals in as many languages as you generate messages.

Text

You must describe the following numerals in the Description field (in the language that you specify in the Language field):

- 1, 2, 3, upto 10
- 20, 30, 40, 50, 60, 70, 80, and 90
- 100
- 1,000
- 10,000
- 100,000
- 1,000,000
- 10,000, 000, and so on

In certain languages, One thousand, One million, and so on are expressed, simply, as 'thousand', and 'million'. If you are defining verbal equivalents of amounts in such a language, do not choose the 'Prefix One' option. Statements and messages printed in such a language will describe amounts such as '1000', simply, as 'thousand'.

Choose the 'Prefix One' option, if you would like amounts such as '1000' described as 'One thousand'.

Currencies

In this screen, you can also describe the pre-decimal and the post-decimal units of a currency in different languages. Enter the verbal equivalent of the 'pre' and 'post' decimal units of a currency in the Pre-Decimal and Post-Decimal fields respectively. For example, if you would like to describe the decimal units of USD, enter:

1. The currency in the Currency field
2. The pre-decimal description as 'Dollars'
3. The post-decimal description as 'Cents'
4. Final Text to be attached to the currency.

You can opt to prefix, or suffix, an amount with its currency. If you would like the suffix an amount with its currency, do not choose the 'Text Before' option. If you would like to prefix an amount with its currency, choose the 'Text Before' option.

For example, if you would like to describe USD 1000, as Dollars One Thousand, choose the 'Text Before' option.

13. Defining Currency Pairs

13.1 Introduction

In the foreign exchange markets, the exchange rates for some currency pairs such as the USD-GBP or USD-JPY are easily obtainable, since these are frequently traded. The exchange rates of other currencies such as the ZAR-INR (South African Rand - Indian Rupee), which is not traded very often, is determined through a third currency. This third currency is usually the US dollar, since the US dollar is quoted in all trading centres.

In the Currency pair definition screen, you define the static attributes of currency pairs for which a regular market quote is readily available. For other pairs, which do not have a regular market quote, you need to specify the third currency through which the system should compute the exchange rate.

The currency pair screen is maintained at the bank level by your Head Office branch using the 'Currency Pair Maintenance' screen.

You can invoke this screen by typing 'CYDCCYPR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Currency Pair Maintenance

New Enter Query

Currency Pair

Currency 1 * Currency Description
Currency 2 * Currency Description
☐ Through Currency

Through Currency

Currency Code Number Of Units ☒ One
Currency Name ☐ Hundred
Quotation Method ☒ Direct ☐ Thousand
☐ Indirect Spread Definition ☒ Percentage
Points Multiplier ☐ Points

Fields

Maker Date Time:
Checker Date Time:
Mod No Record Status
Authorization Status

Exit

13.2 System Features

From among the currencies maintained in the currency screen, the system builds all possible combinations of currencies in pairs. For example, if you have maintained the following currency codes: USD, YEN. The system will give you a choice of defining parameters for the following pairs.

- USD-INR
- USD-YEN
- INR-USD
- INR-YEN

- YEN-USD
- YEN-INR

It is however, not obligatory to define parameters for all these pairs. A currency pair needs to be maintained only if:

- You want to define a direct exchange rate for the pair: for frequently traded currencies like INR-USD or USD-GBP or USD-JPY for which market quotes are available.
- You want to define a through currency for the pair: for those currencies which are not so well traded, market quotes may not be available. Therefore you can route the conversion rate for the pair via a 'through currency'. For example, in the case of GBP-NLG, for which a direct exchange rate may not be available, you can define a through currency say, USD. The exchange rate between GBP-USD and NLG-USD will be picked up by the system to compute the exchange rate between GBP-NLG.

In the absence of a direct exchange rate, the system will look for a through currency to compute the rate. If a 'through currency' has not been maintained then the default local currency will be picked up as the through currency to compute the rate for a currency pair.

13.3 Maintaining Parameters for Currency Pair

Currency Pair

A currency pair (specified as Currency1 and Currency2, in the Currency Pair screen) represents the two currencies for which you need to maintain exchange rates.

To specify the pair, choose from the list provided against Currency1. Select the pair for which you want to maintain parameters.

The pair should be selected according to the quotation method followed by the market, which could be direct or indirect (for details refer to the field 'quotation method'). Exchange rates can be defined for currency1 against currency2 or currency2 against currency1.

The descriptions of the respective currencies are displayed below.

Through Currency

If the exchange rate for a particular currency pair is not to be maintained, specify the 'Through Currency' via which the exchange rate between the currencies should be calculated.

To maintain a through currency for a currency pair, check against the box 'Through Currency'.

Then choose from the list codes provided against Code, Select the currency code, which you want to specify as the 'through currency'. The exchange rate for the currencies involved in the pair will be calculated using the through currency.

Note

- While maintaining a pair involving an 'In' currency ('In' – 'Out' and 'In' – 'In'), you can only specify the Euro as the 'Through Currency'. Please note that you cannot maintain a 'Through Currency' for a pair constituted by an 'In' currency and the Euro.
-

For more details on the manner in which Oracle FLEXCUBE handles the Euro, refer the chapter 'Handling the Euro' in this manual.

Whenever, you define a through currency for a currency pair, you will not be allowed to specify the following for the pair:

- Number of units

- Spread definition

Quotation Method

This is the method to be followed for quoting the exchange rate. There are two methods direct and indirect.

In the Direct method the exchange rate for the currency pair is quoted as follows:

Buy rate = mid rate - buy spread

Sell rate = mid rate + sell spread

Ccy 1 = Rate x Ccy 2

In the Indirect method the exchange rate for the currency pair is quoted as follows:

Buy rate = mid rate + buy spread

Sell rate = mid rate - sell spread

Ccy 2 = Rate x Ccy 1

Example

The market follows the direct quote convention for the currency pair USD-DEM e.g., 1USD=1.6051DEM. To maintain this pair, you would specify currency 1 as USD and currency 2 as DEM, and specify "direct" in this field.

For the USD-GBP pair, which is quoted indirectly (1 GBP = 1, 5021 USD), the USD will be defined as currency 1 and the GBP as currency 2, with the quotation method "indirect".

Number of Units

This indicates the number of units of currency to be used for currency conversion

Spread Definition

You need to indicate the method in which the spread for a currency pair needs to be defined. There are two ways of defining the spread -- in points and in percentage.

The effective spread can be calculated using any of the following two methods:

- In points — spread x points multiplier
- In percentage — spread/100 x mid rate

The method of spread definition that you specify here applies to two instances:

- While maintaining exchange rates for this currency pair
- While maintaining Customer Spread for this currency pair

13.3.1 Specifying Points Multiplier

Points are the smallest unit of measurement in the exchange rate of a currency pair. If you have opted for a points system of defining spread, you should specify the multiplication factor for the points to compute effective spread.

Suppose for the currency pair USD-DEM your rates are as follows:

Mid-Rate:1.6045

Buy rate:1.6040

Sell rate:1.6051

The effective buy spread is 0.0005 (1.6045 - 1.6040) and the effective sell spread is 0.0006 (1.6051 - 1.6045).

In the Rates screen, where you define rates and spreads for a currency pair, you can specify the buy and sell spreads as 5 and 6 instead of as 0.0005 and 0.0006 (i.e., as spread points), and specify here the points multiplier as 0.0001.

The effective spread, buy and sell rates are then computed as follows:

Effective buy spread = Buy spread x Points multiplier = 5 x 0.0001 = 0.0005

Buy rate= Mid rate - Buy spread = 1.6045 – 0.0005 = 1.6040

14. Maintaining Exchange Rates

14.1 Introduction

In the Currency Rates screen, you can maintain exchange rates for a currency pair, the rates at which you buy and sell one currency for another.

A bank determines its buy and sell rate for a currency pair by applying a spread (i.e., its profit margin) to the mid-rate of the currency pair. Mid rate is the basic rate at which a currency pair is exchanged.

The spread applied for a currency pair varies with the transaction type, while the mid-rate usually remains constant. Consequently, different rates are applicable to different transaction types. For instance dollars in currency are purchased at a certain rate, while USD traveler's checks are bought at a different rate. In Oracle FLEXCUBE, you can define a rate type which you would like to associate with a transaction type e.g., 'CASH', 'TRAVCHKS', etc., in the Rates screen.

In the Currency Rates Maintenance screen, you define the mid-rate, buy and sell spread applicable to each rate type; the buy and sell exchange rates are computed by the system.

Buy rates and sell rates can either be maintained by individual branches or can be input by the HO and propagated to all the branches. If in the Bank-wide parameters - Preferences screen you have specified your preference as 'copy exchange rates to branches' then the currency rates maintained at the bank level by your Head Office will be propagated to the branches. In the Bank-wide Preferences screen, if you have not specified 'copy exchange rate to branches' then the 'Currency Exchange Rates Input' screen is maintained at the branch level by the different branches.

Modifications of Rates at branch level are allowed even though "Copy Exchange Rates to Branches" is enabled at bank level.

You can invoke this screen by typing 'CYDRATEE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

◆ Currency Exchange Rates Input

New Enter Query

Currency 1 * Currency 2 *

Currency Rate

1 Of 1 Go

| Rate Type * | Mid Rate | Buy Spread | Sell Spread | Buy Rate |
|-------------|----------|------------|-------------|----------|
| | | | | |

Enrich

Field

Maker
Checker
Mod No

Date Time:
Date Time:
Record Status
Authorization Status

Exit

In this screen you maintain the following parameters for each rate type of a currency pair:

- Mid rate
- Buy spread and Sale spread
- Buy rate and Sale rate

Specify the currency pair for which you want to compute the exchange rates. The pair should be selected keeping in mind the quotation method for exchange rates as followed by the market. The system offers the choice of maintaining both the currencies as currency1 or currency 2 -- USD against DEM and DEM against USD.

For the pair specified the following parameters need to be maintained to arrive at the buy and sell rate of currencies:

- Rate Type
- Mid Rate
- Buy Spread
- Sell Spread
- Buy Rate
- Sell Rate

Rate Type

This is the rate type for which you are maintaining exchange rates for a currency pair. For different transaction categories your bank would like to maintain different exchange rates. For example, traveller's check is purchased at a certain rate whereas a bill of exchange is bought at a different rate.

In the front-end-modules, where you define products to cater to the various transaction types of your bank, you can link an appropriate rate type to the product. For instance, you create a product to cater to outgoing cross currency transfers by SWIFT. For this product, if you define the rate type to be STANDARD then for all contracts linked to this product, the Standard Rate Type would be applied.

Mid Rate

Mid rate is an indicative exchange rate for a currency pair. It is the average of the buy and sell rate quoted by the market for a currency pair.

For example,

currency 1 = USD

Currency 2 = INR

Buy rate -- 1 USD = 1.7020 INR

Sell rate -- 1 USD = 1.7040 INR

Mid-Rate = 1.7030

Buy Spread

This is the buy spread for a currency pair. It can be defined as the profit margin specified over the mid rate when you buy currency 1 for currency2. You can define the buy spread in two ways -- either in points or in percentage. The system computes the effective buy spread for you.

Sale Spread

This is the sell spread for a currency pair. It can be defined as the profit margin specified over the mid rate when you sell currency 1 for currency 2. You can define the sell spread either in points or in percentage. The system computes the effective sell spread for you.

Buy Rate

Buy rate is the rate of exchange for a currency pair, which is computed by the system based upon the mid rate, the spread specified, the spread definition and the quotation method maintained in the 'Currency definition' screen.

Sale Rate

Sell rate is the rate of exchange for a currency pair, which is computed by the system based upon the mid rate, the spread specified, the spread definition and the quotation method maintained in the 'Currency definition' screen.

You can also input the buy and sell rate for a currency pair. In which case, the system will compute the spread for the rate type.

Rate Date

This is a display field. When you enter the exchange rate for a currency pair, the system will default the Rate Date as the Application Date. The rate date will always be less than or equal to the application date.

Rate Serial

This is a running serial number for the Rate Date. You need to specify the serial number. Your entry will be validated for uniqueness. For example, there could be only one exchange rate between USD and EUR for 31/07/2003 with Rate Type STANDARD with Rate Serial as 0001. Thus, this will be a unique rate serial for a currency pair, rate type combination for a given rate date.

When you enter the exchange rate for a currency pair, the system will default the Rate Date as the Application Date and the Rate Serial as the latest available serial for the currency pair + 1. The Rate Serial Number will be system generated. However, you can modify it if required. This number takes into account the Rate Serial Number present in the Currency Rates History screen too. The Rate Serial Number and the Rate Date will be displayed during authorization of the Rate in the Currency Authorization screen.

14.1.1 Authorizing Exchange Rates

Authorization of exchange rates is done from the Currency Exchange Rates input screen. Details like old value, new value for each field (buy rate, mid rate etc) are displayed. Click authorise icon to authorize the record.

14.1.2 Revising Exchange Rates

For revising the exchange rates for your bank or the branches invoke the 'Currency Maintenance' screen. Click the currency pair whose exchange rate you want to revise and click unlock icon on the toolbar. Input/modify the new rates for the pair.

14.1.3 Viewing Exchange Rates

You can view the exchange rates in the 'Currency Exchange Rates View' screen. You cannot input any values. You also have the option of specifying whether you want to view authorized rates or the unauthorized rates for any currency pair.

You can invoke this screen by typing 'CYSRATES' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

| Authorization Status | Record Status | Branch Code | Currency 1 | Currency 2 |
|----------------------|---------------|-------------|------------|------------|
|----------------------|---------------|-------------|------------|------------|

If the branches pick up the exchange rates maintained by the HO, then each time you invoke the 'currency view' screen from a branch it is advisable to update this screen with the latest rate input, from the HO. To do this, click on 'Refresh'. Refresh updates the screen with the last exchange rates input.

14.1.4 Specifying Limits for Cross Currency Transactions

Typically, the exchange rates applicable for cross currency funds transfer or teller transactions is defaulted by the system depending upon the preference indicated in the product preferences, for the product involving the transaction.

In your bank, for high-value cross currency transactions, you may want the user to manually enter the exchange rate involved, rather than let the system automatically pick up a default rate during transaction input.

You can define such a preference to be applicable to cross currency transactions involving:

- A currency pair
- A specific product, or all products
- A specific module, or all modules
- A specific branch, or all branches
- A specific rate code

The transaction amount limit, above which the exchange rate must be entered, for a high value transaction, could be defined in terms of currency pair where the currency of the transaction is currency1 in the CCY pair defined in the maintenance.

To ensure that users manually enter exchange rates for high-value cross currency transactions in Oracle FLEXCUBE, you must specify the limit amounts that must be validated for each transaction in terms of currency pair, product, module, and branch combination. You can use the 'Product Limits Maintenance' screen to specify the limits.

When you have specified these limits, the system automatically validates the amount with each transaction for the currency pair, product, module and branch combination, and accordingly, if the limits are exceeded, enforces the manual entry of exchange rates.

In case, the limit between ccy1 and ccy2 is given in ccy2, the system will automatically convert the transaction amount to an amount in ccy2 using standard mid rate and check against the limit amount whether or not manual entry of exchange rates is required. You can invoke the 'Product Limits Maintenance' screen, by typing 'CSDPXMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

Product Max Limit

New Enter Query

Branch Code *
Module Code *
Product Code *
Currency 1 *
Currency 2 *

Limit Details

| Rate Code * | Limit Currency * | Limit Amount * |
|-------------|------------------|----------------|
| | | |

Fields

| | | |
|-----------|---------------|-------------------------------------|
| Input By | Authorized By | Modification |
| Date Time | Date Time | Number |
| | | <input type="checkbox"/> Authorized |
| | | <input type="checkbox"/> Open |

Branch Code

You must specify the branch for which the limit amount will be applicable. You can specify that the limits must be applicable for all branches.

Module Code

You must specify the module for which the limit amount will be applicable. You can indicate that these limits must be applicable for both the Data Entry (DE) and Funds Transfer (FT) modules.

Product Code

You must specify the product, transactions involving which the limit amount will be applicable. You can specify that the limits must be applicable for all products.

Currency 1

You need to specify the currency1 applicable for defining the Transaction Amount limit, beyond which the system will not default the Auto Exchange Rate.

All valid currencies defined in the Currency Pair Maintenance will appear for selection. This currency is always the transaction currency of the contract.

Currency2

You need to specify the currency2 applicable for defining the Transaction Amount limit, beyond which the system will not default the Auto Exchange Rate.

All valid currencies defined in the Currency Pair Maintenance will appear for selection. The Currency2 should be part of a Currency Pair Maintenance in which the Currency1 defined here is the first currency. Currency 2 can be specified as ALL.

14.1.4.1 Specifying Limit Details**Rate Code**

You need to specify the Rate Type (code) for the Exchange Rate Limit

Limit Currency

You need to specify the currency in which the Limit Amount should be expressed. All valid currencies defined in the system will be applicable for selection. There will be a validation for the limit currency as either Currency1 or Currency2.

Limit Amount

You need to specify the maximum amount up to which the system should default the Exchange Rate or perform the Rate Variance validation.

14.1.4.2 Validating Exchange Rate Limits

The Funds Transfer Contract Input will default the Rate only if the Transaction Amount is less than the Maximum Amount defined for the Rate Code maintained at the product level for FT. If the amount is more than the specified amount, then the system will not default the Rate. Instead, it will force the user to enter the Rate. Once the user enters the Rate, the system will not add the Customer Spread etc. as this will be final Exchange Rate for the contract.

The Rate Variance validation will also be done only if the amount is less than the maximum amount defined for the Rate Code maintained at the product level for FT. If the amount is more than the specified amount, the system will not perform the Rate Variance validation. Instead, there will be an override to specify that the transaction amount is greater than the maximum amount for Rate Variance check.

For details about how limits are applied when a transaction is entered, refer the chapter Processing a Funds Transfer, in the Funds Transfer user manual.

15. Maintaining Currency Spread for Customer

15.1 Maintaining Customer Spread Details

For a customer and currency pair, you can maintain tenor-wise spread details in the 'Customer Spread Maintenance' screen.

You can invoke this screen by typing 'CYDCUSPR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

| Tenor * | Buy Spread | Sale Spread |
|---------|------------|-------------|
| | | |

In this screen, for a customer and currency pair, you can maintain buy and sell spreads for different tenors.

You need to maintain customer spreads in each branch. Transactions initiated in a branch will pick up the spread(s) maintained for that branch.

Note

- Funds Transfer, Loans and Deposit contracts have tenor = 0 (zero). Therefore, you need to maintain Customer Spreads for zero tenor also.
 - The tenor is specified in days
-

15.1.0.1 Specifying Spread Details

When processing an FX deal involving a customer (for whom you have maintained spread details), the system picks up the customer spread corresponding to the tenor of the deal and builds it into the exchange rate. If spread details are unavailable for a specific tenor, the system picks up the spread defined for the nearest lower tenor.

For example, assume for a customer and currency pair you maintain spread details for the following tenors: '3', '5', and '10' days. When processing a deal with a tenor of '4' days (involving the customer and the currency pair), the system picks up the spread details defined for a tenor of three days. This is because spread details for a '4' day tenor is unavailable for the customer and currency pair.

Note

You can also maintain customer spreads for the wildcard entry – ALL. If spread details for a specific counterparty (for the currency pair) are unavailable, the System looks for the customer spread maintained for the wildcard ALL entry. If even that is not available, then the customer spread defaults to zero.

15.1.1 **Computing Buy and Sell Spreads**

Using percentage system -- suppose the bank wants to make a profit of 5% over and above the mid rate quoted. Suppose the dealing currencies are USD and AUD. 1USD = 1.4166 AUD for Standard rate type. (Mid rate being 1.4166). Now to arrive at the spread the bank will use the following formula:

$$\text{Spread} = 5 / 100 \times \text{Mid rate (1.4166)} = 0.07083$$

Using the points system -- suppose the point quoted by the bank is 708.3. The points multiplier in this case would be 0.0001 (depends on the decimal points that the mid rate extends to. Usually it is 4 decimal places).

$$\text{Spread} = \text{Points (708.3)} \times \text{Points Multiplier (0.0001)}$$

Now coming to the buy and sale rate computing, there are two ways of computing the buy and sale rates -- Direct and Indirect. Depending upon the quotation method you have specified in the Currency pair screen, the system computes the spreads.

In the **Direct** method, the buy and sell rates are calculated as follows:

$$\text{Buy Rate} = \text{Mid-Rate} - \text{Buy Spread}$$

$$\text{Sell Rate} = \text{Mid-Rate} + \text{Sell Spread}$$

For cross currency contracts, the rate for the currency pair is:

$$1 \text{ unit of Ccy 1} = \text{Rate} \times 1 \text{ unit of Ccy 2}$$

In the **Indirect** method, the buy and sell rates are calculated as follows:

$$\text{Buy Rate} = \text{Mid-Rate} + \text{Buy Spread}$$

$$\text{Sell Rate} = \text{Mid-Rate} - \text{Sell Spread}$$

For cross currency contracts, the rate for the currency pair is:

$$1 \text{ unit of Ccy 2} = \text{Rate} \times 1 \text{ unit of Ccy 2}$$

The method of spread definition – percentage or points – that you have maintained for the currency pair is displayed on this screen.

15.1.2 **Maintaining Currency Margins for Customer**

For each customer of your bank you can define buy and sell margins for a specific currency. This spread is applied to floating interest components that involve the customer and currency combination.

You can define buy and sell margins for a customer in the Customer Spread Maintenance screen invoked from the Application Browser. You can invoke this screen by typing

'CFDCUMRG' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The margin that you define will be appropriately picked up and applied to arrive at the final rate that is applied to floating components of contracts that involve the customer - currency combination.

The buy and sell margins that you define are for a customer and currency combination. You can select the customer and currency combination from the option lists available.

For the selected currency – customer combination, you can define amount slabs and specify a Borrow and Lend margin for each slab. To add a slab to the list click add icon and enter the slab details. To remove a slab from the list, highlight it and click delete icon.

Whenever you enter a contract in Oracle FLEXCUBE that involves the customer and currency combination, the appropriate spread is applied to arrive at the floating rate to be charged. The slab is selected based on the contract amount and depending on the nature of the contract, the Borrow or Lend spread is applied.

Customer Spread Maintenance

New Enter Query

Customer * Currency *

Borrow/Lend ☒ Borrow ☐ Lend

Customer Spread Maintenance

| Amount Slab | Spread |
|-------------|--------|
| | |

Fields

Input By Date Time Authorized By Date Time Modification Number

☐ Authorized ☐ Open

15.1.2.1 Making Margin Applicable to All Customers

For a given currency, you can define borrow and sell margins to be applied to All customers. At the customer field choose ALL. However, if you have maintained currency margins for a specific customer and currency combination, it takes precedence over the margin defined for all customers.

Currency margins can be maintained for customers across branches. In effect, a branch can maintain margins for a customer belonging to another branch. These margins are propagated across branches of your bank.

16. Period Code Maintenance

16.1 Introduction

Banks, like all business houses compute their profits and losses and assess their financial position at the end of each financial year, which typically extends to 12 months -- from January to December or from March to April. However, this could be changed, depending upon the Bank's policies and regulatory requirements.

For interim reporting needs, the financial year is further divided into accounting periods, the duration of which is again determined by the bank's accounting requirements. For example, your bank's Board of Directors meets once a month therefore, you would divide the financial cycle into monthly periods.

The financial year and the accounting periods are referred to in the Oracle FLEXCUBE system as the 'Financial Cycle' and the 'Financial Periods' respectively and are maintained at the bank level by your Head Office branch.

At the end of each financial period and financial cycle you can generate profit and loss statement and a balance sheet. The system also offers you the flexibility of keeping a financial period/financial cycle open, allowing you to post adjustments to it and obtain a revised profit or loss statement/balance sheet. You can maintain these details in the 'Period Code Maintenance' screen.

16.2 Invoking Period Code Maintenance Screen

You can invoke this screen by typing 'STDPRCDE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

Period Code Maintenance

New Enter Query

Financial Cycle

Financial Cycle *
Description
Start Date *
End Date *

Period Group

1 Of 1 Go

| Period Code * | Start Date | End Date * |
|---------------|------------|------------|
| | | |

UDF

Maker
Checker
Mod No

Date Time:
Date Time:
Record Status
Authorization Status

Exit

In this screen you define the following:

- The financial cycle of your bank giving the start date and end date of each financial year
- The period group - financial periods into which each financial cycle is to be divided

The following are the features of the Period Code screen

Financial Cycle

For each financial cycle you maintain the following parameters:

Cycle

This is a code for the financial cycle. It acts as an identifier for the cycle. For example, while posting adjustments into a previous financial cycle -- you would identify the year through this code.

Input the code using a maximum of 9 characters, alphanumeric.

For example, the financial cycle extends from 1st April to 31st March in India. A bank here could define its code for the year 1996-97 as FY 1996-97.

Description

This describes the financial cycle. Enter description using a maximum of 35 characters, alphanumeric. Taking the above example, you could enter Financial Year - 1996-97.

Start Date

This is the first day of this Financial Cycle

End Date

This is the last day of this Financial Cycle

Period Group

The financial cycle defined above, can be divided into different accounting periods. To define individual accounting periods click on the first row under period code. A period called 'FIN' is created by the system. This is an open ended period coinciding with the last day of the financial cycle (for details refer to the section 'System Functions').

You can maintain the following parameters for each accounting period within a financial cycle:

Period Code

This code identifies the accounting period. Enter a code using a maximum of 3 characters, alphanumeric. For example, if your period length is a quarter you can enter - Q1 for the first period; Q2 for the second; Q3 for the third and so on. If your period length is a bimonthly you can enter BM1, BM2. If your period length coincides with a month you can input M1, M2.

Start Date

This is the first day of the corresponding period

End Date

This is the last date of the corresponding period. 'End date' of a period should always end on a month end. Please note:

- The period codes could be of varying lengths but no gaps should be left between periods
- The duration of two periods should not overlap
- You can modify the period code of the current or a future period; however, a past period cannot be modified even if it has not been closed
- All details maintained in the 'Period Code Screen' will automatically apply to any new branch opened by you in the Branch Parameters Screen

- The current financial cycle code and the current period code are displayed in the 'Branch Parameters Screen'

Period Code Status

After authorisation, you can view whether a financial period is open or it has been closed. Each branch can view the status of a period in every other branch. Click the period whose status you want to view.

Branch

Displays the codes of the different branches of your bank

Status

Displays the corresponding status of the period code highlighted. 'O' - indicates open status; 'C' - indicates closed status

Note

The current financial cycle code and the current period code are displayed in the 'Branch Parameters Screen'

All details maintained in the 'Period Code Screen' will automatically apply to any new branch if incorporated to your bank post maintenance of this screen. The status of all periods in the new branch will be open.

16.3 System Functions

The system offers you the flexibility of posting transactions into a previous accounting period which has passed its due end date. For example, let's assume your bank's financial cycle extends from 1st January to 31st December; the first period starts on 1-01-96 ends on 31-03-96. Even beyond 31-03-96 you can keep the period open to be able to post for example, expense bills you expect to receive in April. After you have posted all adjustments, you can close the period.

Even after you have closed the last accounting period of a year, the system offers you the flexibility of posting adjustments to the financial year.

For each financial year the system generates an open status period called FIN. Its start and end dates coincide with the last date of the financial cycle. Into this one day period you can post the accumulated profits and loss for the financial cycle, general reserves, and statutory reserves for the current year after paying off the dividends. After this one day period is closed the status of the financial cycle in the made by field 'status' is displayed as closed. With this the financial year stands closed and no adjustments can be posted to it.

Closure of a period/financial cycle can be invoked through the General Ledger/ Core Services module. The branches of the bank should close this period/financial cycle.

17. Status Code Maintenance

17.1 Introduction

Loans and bills, which are past their due maturity date of installment re-payment, but remain unpaid, are defaulted contracts. In the Oracle FLEXCUBE system these defaulted contracts can be assigned to different statuses, based on the number of days for which the contract is outstanding.

Each status can be assigned a code. For instance, you can define a status code PDO to represent 'past due obligation', and specify a period of 15 days after which an outstanding contract should be marked as 'PDO'. If they are due for more than 60 days, you could assign a 'doubtful' status; 'sub-standard' if due for 6 months, and so on. Contracts for which no installments are due, or which are regularly paid on their due dates are assigned the status 'Active' by the system. According to the number of days of default defined for each status, a loan would be moved from 'Active' to PDO status, then to doubtful and finally to sub-standard status.

Similarly, you can define status codes for current and savings accounts also. Current and Savings accounts that have not generated any interest over a specific period or have remained inactive with interest overdue may be identified as 'NPAs' (Non-Performing Asset). In Oracle FLEXCUBE, you can assign these accounts different status codes and define status criteria based on which the status movement will occur.

Refer the 'Core Entities' user manual for details on associating status codes with a customer account class /account.

These status codes are maintained in the 'Status Codes Maintenance' screen.

17.2 Invoking Status Maintenance Screen

You can invoke this screen by typing 'STDSTSCD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Status Code Maintenance' application window. The title bar reads 'Status Code Maintenance'. Below the title bar is a toolbar with 'New' and 'Enter Query' buttons. The main workspace contains four input fields: 'Status Code *', 'Description', 'Status Sequence *', and 'Status Type *' with a dropdown menu currently set to 'Both'. At the bottom of the window, there is a 'Fields' section with labels for 'Maker', 'Checker', 'Mod No', 'Date Time:', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

In this screen you can maintain the following to user defined status of a loan or bill/account status:

- A unique code for the status
- A brief description for the status
- A sequence number for the status
- The type of status – Indicate whether the status codes are maintained for an 'Account' or for a 'Contract', or for 'Both'

The type of status you choose depends on the status processing basis for your branch, which is defined in the Branch Parameters Preferences maintenance. If status processing basis is at individual account / contract level, you can choose the applicable status types as 'Account' or 'Contract'. The status codes that have been maintained of type 'Account' are available for association in the Account maintenance and those maintained with type 'Contract' can be associated with contracts.

If status processing basis is at Group / CIF level, you can only maintain status codes of type 'Both' (that is, applicable for both accounts and contracts). In such a case, you must associate the statuses at both the Account maintenance as well as for contracts.

Note

- It is mandatory to maintain the status code 'NORM' (Normal) with the sequence number as '0', for all the status types. The sequence number must not be repeated for a status type.
 - The sequence number associated with the status will be used for determining the hierarchy of statuses, i.e., higher the number, worst the status and this will be unique for the status codes.
-

17.2.1 **Maintaining Status Codes for Contracts**

The following parameters need to be maintained for defining a status code:

Status Code

This is the code, which identifies the status to which the contract belongs.

For example, assign a code using a maximum of 3 characters, alphanumeric. For example, if your contract has past its due obligation status you can input code PD1. PD representing post due obligation. The number 1 stands for stage 1 of the post due obligation status

Status Description

This is the description of the status, Enter a description using a maximum of 35 SWIFT characters.

For example, taking the above example, you can input here - Past Due Obligation 1 for Loan if you are maintaining status codes for Loans.

Link to

This represents the category of the product - asset or liability to which the contract status is applicable.

For example, if you are maintaining status codes for loans or any money market placements, click on 'assets type of product'. If you are maintaining status codes for deposits, click on 'liability type of products'.

Effective days from Maturity

This indicates the number of days after the due date when this status becomes applicable to the contract. You can specify any number of days from 0-999.

The effective days defined here is defaulted to the product level in the Bills and Loans modules. You have the option of redefining the number of days at the product level.

17.2.2 Maintaining Status Codes for OD Account

Oracle FLEXCUBE provides a facility to maintain status codes for Charge-off and Write-off status of the OD account. These status codes are maintained in 'Status Code Maintenance' screen and the details of the same are as follows:

| Status Code | Description | Status Sequence | Status Type |
|-------------|--------------------------------------------------|---------------------------------------------|-------------|
| CROF | Status code for Charge-off of OD accounts. | Should be less than SUSP status sequence | Account |
| SUSP/WOFF | Status code for suspended status of OD accounts. | Should be greater than CROF status sequence | Account |

17.3 Maintaining Dormancy Parameter Details

You can maintain the dormant statuses for the customer account in the 'Dormancy Parameter Maintenance' screen. To invoke this screen, type 'STDSTDOR' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

Transaction Branch

Select the appropriate branch from the list of branches available in the option list. This screen will be available only for those users who has 'Multi Branch Operational' check box enabled at 'User Maintenance' Screen.

While clicking 'Ok' button, the system validates the access rights of the selected branch and function for the user. If you don't have appropriate rights on the selected branch and function, the system would raise an error message. If you select a valid branch, the system updates the same as transaction branch and the transaction would be posted for this branch.

Note

The system performs the action level access rights validation only on 'Save' operation.

After selecting the Transaction Branch, you can enter the remaining details in the 'Dormancy Parameter Maintenance' screen.

You need to specify the following details:

Branch Code

Specify the branch code. The adjoining option list displays all the branch codes that are maintained in the system. You can choose the appropriate one.

Customer A/C

Specify the customer account for which you are maintaining the dormant status. The adjoining option list displays all the customer account numbers that are maintained in the selected transaction branch. You can choose the appropriate one.

Debit

Check this box to indicate that no debits should be posted to the selected customer account.

Credit

Check this box to indicate that no credits should be posted to the selected customer account.

Frozen

Check this box to indicate that the customer account is frozen due to some unavoidable reason.

Dormant

Check this box to indicate that the account is in dormant status which means not used for along time.

Dormant Param

Indicates the parameters for re-activating the dormant account. You can select one of the following options:

- Debit
- Credit

- Any

Manual

Remarks

Specify the remarks, if any.

17.4 Maintaining CR\DR Statistics Details

You can maintain the credit\debit statuses for the customer account in the 'CrDrStat Maintenance' screen. To invoke this screen, type 'STDSTCDM' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

Transaction Branch

Select the appropriate branch from the list of branches available in the option list. This will be available only for those users who has 'Multi Branch Operational' check box enabled at 'User Maintenance' Screen.

While clicking 'Ok' button, the system validates the access rights of the selected branch and function for the user. If you don't have appropriate rights on the selected branch and function, the system would raise an error message. If you select a valid branch, the system updates the same as transaction branch and the transaction would be posted for this branch.

Note

The system performs the action level access rights validation only on 'Save' operation.

After selecting the Transaction Branch, you can enter the remaining details in the 'CrDrStat Maintenance' screen.

The screenshot shows a window titled "Credit Rating Status" with a menu bar containing "New" and "Enter Query". The main area contains the following fields and controls:

- Branch Code *
- Customer A/C *
- ☐ No Debit
- ☐ No Credit
- ☐ Posting Allowed
- Remarks

At the bottom, there is a "Change Log" section with a table structure:

| Maker | Date Time: |
|---------|----------------------|
| Checker | Date Time: |
| Mod No | Record Status |
| | Authorization Status |

An "Exit" button is located in the bottom right corner.

You need to specify the following details:

Branch Code

Specify the branch code. The adjoining option list displays all the branch codes that are maintained in the system. You can choose the appropriate one.

Customer A/C

Specify the customer account for which you are maintaining the credit\debit status. The adjoining option list displays all the customer account numbers that are maintained in the selected transaction branch. You can choose the appropriate one.

No Debit

Check this box to indicate that no debits should be posted to the selected customer account.

No Credit

Check this box to indicate that no credits should be posted to the selected customer account.

Posting Allowed

Check this box to indicate that the account class being created is to be used while creating IRA monetary accounts. Monetary accounts used for IRA need to be distinguished from the other accounts in Oracle FLEXCUBE, so that these accounts do not come up for posting in the other Oracle FLEXCUBE screens.

Remarks

Specify the remarks, if any.

18. Transaction Code Maintenance

18.1 Introduction

In the 'Transaction Codes Maintenance' screen you define transaction codes to representing various types of transactions, for example, transfer charges, incoming mail transfer, incoming telex transfer, reserve, incoming clearing transfer etc. All similar transactions can be grouped under a common transaction code with a description. This description will be printed on the account statements, reports and advices generated.

For a transaction type you also maintain other related processing details which will be applicable to all transactions posted under a common code. Details about availability of funds for liability checking, SWIFT code for the transaction type, preferences regarding charges to be levied on turnovers, payment to be made through cheques etc.

18.2 Invoking Transaction Code Screen

You can invoke 'Transaction Code Maintenance' screen by typing 'STDTRNCD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Transaction Code Maintenance' window. It includes sections for Transaction Details, Availability Information, Overdraft Tracking, Preferences, and Anti Money Laundering Monitoring. The bottom section is labeled 'Fields' and contains labels for Maker, Checker, Mod No, Date Time, Record Status, and Authorization Status. An 'Exit' button is located in the bottom right corner.

In this screen you maintain the following for a transaction:

- A code representing the transaction type
- Description of the transaction type
- The interval after which funds should be made available after the transaction
- Preferences regarding charges to be levied or not on number of transaction counts and total turnover amounts

- Preference stating whether a transactions booked under this code should cause an account marked as 'dormant' by the system to be re-instated to 'active'
- Preference whether payment for a transactions posted under this code should be made through cheque
- Preference indicating whether payment for a transaction booked under this code should be considered for Escrow transfer processing

18.2.1 Maintaining Transaction Details

The following parameters need to be maintained for a transaction type:

Transaction Code

This is the code you assign to a transaction type. This code identifies the type of transaction.

Enter 3 characters, Alphanumeric. For example, for all transfer charges transaction you can give the code as TCT; for incoming telex transfer you can input - ITT. In case, you want to assign numeric codes only, then for ease of operation similar transaction types should be grouped into a range. For example, you can set a range for all Money Market transactions say, A1-A30; a different range for Bills and Collections B1-B30 and so on.

Description

This is the description of the transaction type

Enter the description using a maximum of 35 characters, alphanumeric. For example, for TCT code you can enter 'Transfer Charges Transaction'.

SWIFT Code

This is the SWIFT code to which this transaction code is linked. It is used for posting transaction details on SWIFT format.

Select from the option list. It will display a list of SWIFT formatted codes representing transaction types. The following list is displayed:

| SWIFT CODES | TRANSACTION TYPE |
|--------------------|-------------------------------------------|
| BOE | Bill of Exchange |
| BRF | Brokerage fee |
| CHG | Charges and other Expenses |
| CHK | Cheques |
| CLR | Cash Letter/Cheque Remittance |
| COL | Collections |
| COM | Commission |
| DCR | Documentary Credit (for Principal Amount) |
| DIV | Dividends - Warrants |
| EQA | Equivalent Amount |
| ECK | Euro checks |
| FEX | Foreign Exchange |

| | |
|-----|-----------------------|
| INT | Interest |
| LBX | Lock Box |
| LDP | Loan Deposit |
| MSC | Miscellaneous |
| RTI | Returned Item |
| SEC | Securities |
| STO | Standing Order |
| TCK | Travelers Cheques |
| TRF | Transfer |
| VDA | Value Date Adjustment |

The codes COL -Collections, DCR - Documentary Credit and SCC- Securities are used when entering a principal amount.

MIS Head

Each Transaction Code that is created can be linked to an MIS Head. An MIS Head indicates the manner in which the type of entry should be considered for profitability reporting purposes.

18.2.1.1 Indicating Availability Information

This states the different time intervals after which funds will be available for withdrawal in case of all transactions posted under this transaction code.

The system defaults to immediate, which means that funds will be immediately available for withdrawal (the immediate option on the screen). Example: Teller Transaction. For all Clearing transactions you have the option to specify as to when will funds be made available for withdrawal. Click the desired option.

Click 'On Value Date' option if you want funds to be available on the date the transaction became effective. Example: A loan or a deposit

Incase you want to specify the number of days after which funds should be available for withdrawal, click on the option After Days. Enter the number in the box. It could be any two digit positive integer from 1 to 99. This option will make funds available for all transactions posted under this code, on the specified date from the value date. Example: Demand Draft

When you click the last option that is, After Days with New Value Date and enter the number of days in the box; then the original value date of the contract will take a new value date. This new value date = old value date + the number of days input by the user in the box against the option. Example: Future dated funds transfer.

The difference between the third and fourth option being that in the latter case the old value date changes; while in the former the value date does not change.

Intra-day Release

If you want uncollected funds on a transaction posted using the transaction code, to be manually released intra-day (that is, within the day), select the Intraday Release option. The Intraday Funds Batch, when manually executed during the day, picks up those transactions that are due for release on or before the system date, which have been posted with the transaction code (with the Intraday Release option enabled), for release of uncollected funds.

The Intraday Release option cannot be enabled if the Availability specified for the transaction code is Immediate.

You can use the ACUNCOLB (Intraday Funds Release) batch process to perform the intra-day release of uncollected funds in respect of transactions posted using a transaction code for which the Intraday Release option has been enabled.

For details about invoking the batch process, refer the Current and Savings Account user manual.

18.2.1.2 Tracking Overdraft

Component type for transaction

Select the component type for transaction from the drop-down list. The options available are:

- Principal - Select 'Principal', if a transaction type is not an interest or charge
- Interest - Select 'Interest', if a transaction code is used for debiting interest for an overdraft account.
- Charge - Select 'Charge', if a transaction code is used for debiting charge for an overdraft account.

The component type for the transaction code is mandatory for maintaining transaction code and cannot be modified after the first authorization.

18.2.1.3 Specifying Preferences

This field indicates your preferences regarding transactions booked against this transaction code. The preferences marked relate to the following:

Interest and Charges Transaction Count

Every debit or credit entry is passed under a transaction code. If for a transaction code you have checked 'I&C transaction count' then all entries made under that code would be picked up by the system as chargeable transaction counts which would be used by the I&C system to compute charges.

Therefore, you should take care not to check for all bank induced transactions like - service charges, interest payment, calculation, brokerage and charges, etc.

For example, your bank has a policy of limiting savings withdrawals without additional charges to only 8 in a month. Beyond which all withdrawals would be charged. For the ninth and onward withdrawals in the month from any account the system will maintain a count for computing charges. However, care should be taken to exclude all bank-induced transactions from the count.

Interest and Charges Turnover inclusion

Every debit or credit entry is passed under a transaction code. If for a transaction code you have checked 'I&C turnover inclusion' then the debit turnover/ credit turnover balance under that code would be picked up by the system as chargeable depending upon the option specified in the I&C module. Therefore you should take care not to check for all bank induced transactions like - service charges, interest payment, calculation, brokerage and charges, etc.

Interest and Charges Balance Inclusion

Check this box to indicate that the transactions posted under this code should be considered for the purpose of computation of Remuneration (Interest). By default this option is checked. Uncheck this box for such loan transactions or any other transactions for which you wish to exclude computation of remuneration (interest).

Note

Once the transaction code is authorized, you cannot change your preference.

Consider for Turnover Limit

Check this box to indicate that all transactions posted under this code should be considered as part of the turnover limit processing.

Consider for Cover Sweeps

Check this box to consider easy saver processing using cover accounts for transaction.

Only if you check this box, the system will consider the debit transactions for sweep from cover accounts/auto linked TD/linked term deposits.

If a particular transaction should not be included for sweep, then the related transaction codes should be maintained with 'Consider for Cover Sweeps' as unchecked.

The above field is applicable only for clearing and teller modules. Oracle FLEXCUBE repays loan from multiple accounts. In Oracle FLEXCUBE, the loan account is the primary account and all the other accounts linked to it are cover accounts. While paying the settlement if the primary account has insufficient amount, the system will check the cover accounts for the remaining amount according to the preference.

Consider for Account activity

If you check the field 'Consider for A/C activity' for a transaction code, then any debit or credit posted under this code would reinstate the status of an account from dormant to active and accounting activity shall be considered.

Cheque Mandatory

If for a transaction code you check 'Cheque Mandatory' then, for all transactions posted under this code, transaction will take place through cheque. For example: Incoming Clearing transfer.

Cheque Mandatory should be checked only for SB cheque withdrawals and Cash Account Cheque withdrawals.

Available Balance Check Required

Select this option if you want the system to check for the availability of funds before posting a debit entry to a customer account. The system will check for the available balance in all customer accounts associated with the Transaction Code for which the option is enabled. If the available balance check fails i.e. if the system detects insufficient funds in the customer account, it will display a warning message.

Note

However, the system will check for the available balance only if you have selected the 'Available Balance Check required' option for both the transaction code associated with the accounting entry and the Customer Account Class to which the customer's account that is being debited, belongs. The check will not be performed if the option is not selected in both places.

Interest and Charges Penalty Inclusion

In the transaction code that you use for debit entries to time deposit accounts, you must indicate the computation of penalties on debit entries due to withdrawals from the account before the maturity date. You must select the IC Penalty Inclusion check box to indicate this.

Inter Branch in Local Currency

This indicates whether inter branch entries passed with this transaction code should be in Local currency. If this option is checked, the inter branch transactions would be passed in local currency. This way, the Treasury would be able to track its profit and the branch's profit by passing a single consolidated entry (Position transfer from one branch to the Treasury branch) at the treasury rate.

Note

- This option is applicable only if the local currency of the different branches is the same. This option is applicable only for Fcy1- Fcy1 transactions. For other transactions, namely, Fcy1-Fcy2, Lcy-Fcy, Fcy-Lcy, IB entries would be based on IB Parameters Maintenance.
 - For position transfer, the 'Inter Branch in Local Currency' check box in the Transaction Code maintenance screen should be checked to avoid creating position due to IB posting.
-

Acumen Transaction Code

You need to check this option in order to eliminate the deals/transactions uploaded from the Acumen in the Hand-off of transactions affecting FCY Position to Acumen from Oracle FLEXCUBE.

Note

This is applicable where Oracle FLEXCUBE interfaces with Acumen. Acumen is an Integrated Turn-key solution for Treasury, Derivatives and Capital Markets Covering Front, Risk Control, Middle Office from Login SA.

Exempt Advance Interest

Check this box to indicate that all the postings with this transaction code should not be considered for penalty interest calculation.

Escrow Processing

Check this box to indicate that all the payments related to this transaction code should be considered for Escrow sweeps. If this box is checked and the credit account (Project account) is Escrow enabled then the system will automatically compute predefined percentage of transaction amount and places an amount block on the credit account (Project account).

Note

Escrow processing is possible only if the trust account and escrow account are of the same currency and are with-in Oracle FLEXCUBE.

Available Balance update through PPC

Check this box to update the available balance on the project through PPC.

Salary Credit

Select the type of salary credit from the adjoining drop-down list. This list displays the following values:

- Normal Salary
- Bulk Salary

By default, the system selects null value.

Note

- The value 'Bulk Salary' can be selected only if the 'Availability Information' is 'Immediate'.
 - This applies when you use the option 'Bulk Salary' along with a transaction code. When a credit is made to an account through salary upload table along with a bulk salary enabled transaction code, the system blocks the entire credit amount on that account with effect from the date of upload. This block remains active for the period maintained in CSTB_PARAM against the parameter 'BULKSALARY_BLOCK_DAYS'. The number of days for expiry is mentioned terms of calendar days. The system does not allow manual operations on the amount block for these accounts.
-

Statement Day Basis

You need to specify when the transaction associated with the selected Transaction Code should appear in the account statement. The available options are:

- Current Working Day
- Previous Working Day

18.2.1.4 Accounting Entry Processing to Calculate Statement Date

The accounting entry processing will be enhanced to calculate the Statement Date based on the Transaction Code Maintenance and the Statement Status at the Branch level. The following illustration explains the calculation of Statement Date.

Assume two Transaction Codes TXN1 and TXN2 have been defined with Statement Date Basis as Current Working Day and Previous Working day respectively. The Statement Date would be derived as follows:

For a transaction C1 posted on say 25th Jan, 2004 with TXN1, the Statement Date would be derived as 25th Jan, 2004 irrespective of the Branch Statement Status.

For a transaction C2 posted on 25th Jan, 2004 with TXN2, the Statement Date would be derived as the Previous Working Day of 25th Jan, 2004 if the Branch Statement Status is set to 'N' specifying that the Branch is not yet ready for periodic statements processing.

For a transaction C3 posted on 25th Jan, 2004 with TXN2, the Statement Date would be derived as 25th Jan, 2004 if the Branch Statement Status is set to 'Y' specifying that the Branch is ready for periodic statements processing.

The Statement Date would be stored as part of the archived data also

The Statement Date would be recomputed during the reversal entry in the same logic

18.2.1.5 Monitoring Anti Money Laundering**Anti Money Laundering Required**

Check this box to indicate that AML monitoring is required for all accounting entries linked to the particular transaction code. Leave it unchecked to indicate otherwise.

Product Category

If you indicate that AML tracking is required for all transactions linked to the particular transaction code you have to identify the product category for which AML tracking is necessary.

18.2.2 Maintaining Country Name Details

You can define country name through the 'Country Code Maintenance' screen. You can invoke this screen by typing "STDCNMNT" in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Country Code Maintenance' application window. It features a title bar with a diamond icon and the text 'Country Code Maintenance'. Below the title bar is a menu bar with 'New' and 'Enter Query' options. The main area contains two columns of input fields. The left column includes 'Country Code *', 'Alternate Country Code', 'Limit Currency', and three checkboxes: 'Blacklisted', 'EU Member', and 'Generate 205'. The right column includes 'Country Name', 'ISO Country Code', 'Overall Limit', two checkboxes: 'IBAN Mandatory for Payment Messages' and 'Clearing Code in BIC+', 'Default Clearing Network', and 'International Dialing Code +'. At the bottom, there is a 'Fields' section with labels for 'Maker', 'Checker', 'Mod No', 'Date Time:', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

Here, you can capture the following details

Country Code

You can capture a unique three-character code to identify the country. For example: you can maintain USA as the country code for United States of America.

Alternate country code

You can also associate an alternate country code. This is for information purposes only and will not be printed on any customer correspondence.

For example you can have US as the alternate code for USA

Country Name

After you define an alphanumeric code to identify the country for which you would like to assign a name, you have to specify the name of the Country.

Overall Limit

This is the maximum credit exposure that a bank is willing to take for a country. That is, the sum of all utilization's under this country liability cannot exceed the amount specified here.

Blacklisted

Further, in the 'Country Name Maintenance' screen you can black list a country for further usage. You are not allowed to deal in countries that are blacklisted.

You can only deal with countries that are *not* blacklisted

IBAN Mandatory for Payment Messages

If this is checked, it indicates that for every payment message an IBAN is mandatory. This is automatically checked if you have checked the 'EU Member' box.

If this option is unchecked for a country, the system will not process the outgoing payments wherein the ordering customer or the beneficiary customer belongs to that country.

EU Member

This indicates whether the country is recognized by Swift as a part of the Intra European countries.

If you check this flag the instructed amount field should be mandatory in the generated 103, 103+ and 102 messages. The instructed amount field is mandatory in the incoming messages.

Clearing Code in BIC+

Check this box to indicate that the National ID in the BIC plus file is the clearing code. During upload of clearing codes from BIC plus file, the records that belong to countries against which this box is checked will be selected.

Generate 205

Check this box to indicate that the cover message 205COV or 205 need to be generated for transactions involving this country. If you do not select this option, RTGS, 202 or 202COV message will be generated.

For more details on 202COV and 205COV cover message formats, refer settlements user manual.

Default Clearing Network

Once the National ID from BIC plus directory is uploaded into clearing codes, the network will be populated as the default clearing network for that country. This is mandatory when clearing code in BIC+ is chosen as 'Y'.

International Dialling Code

Specify the international dialling code associated with the country.

19. Account Revaluation Maintenance

19.1 Introduction

Account revaluation is a process by which the LCY equivalent of balances in the FCY accounts is marked to market.

In all foreign currency accounts, the FCY current balance is displayed along with the LCY equivalent of the current balance. The LCY equivalent current balance is the aggregate of the LCY equivalent of the various transactions that have been posted to the account.

In the 'Chart of Accounts - GL Details' screen you specify whether a GL should be revalued or not.

In the 'Account Revaluation Maintenance' screen, you specify parameters for account revaluation such as rate type, the GL to which the profit or loss from revaluation should be posted, etc. You can invoke this screen by typing 'RVDSETUP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Account Revaluation Setup

New Enter Query

General Ledger Code *
Description

Transaction Code *
Description

Rate Type *
Description

Profit General Ledger
Description

Loss General Ledger
Description

Revalue Into
Description

Trading Profit GL
Description

Trading Loss GL
Description

☐ Netting of Offset Entries

Entry Based Revaluation

Rate Type
Transaction Code

Fields

| Input By | Authorized By | Modification Number |
|-----------|---------------|-------------------------------------|
| Date Time | Date Time | |
| | | <input type="checkbox"/> Authorized |
| | | <input type="checkbox"/> Open |

In this screen you can maintain the following parameters to define the revaluation parameters for a GL account:

- I The general ledger accounts to which the profit or loss on revaluation is to be posted
- I The account to which the revaluation profit is to be debited or loss credited
- I The rate type to be used to revalue the GL
- I The transaction code for posting the revaluation entries

- | The rate type to be used for accounting entry-based revaluation of profit and loss GLs
- | The transaction code that would be used to post revaluation entries due to accounting entry-based revaluation of profit and loss GLs

General Ledger Code

This is the code of the GL account for which you are specifying revaluation parameters.

Transaction Code

This is the transaction code under which the accounting entries would be posted to the defined revalued GL account

Rate type

This is the rate type to be used for revaluation of this GL

Profit General Ledger

If the result of revaluation is a profit, the profit amount is credited to this profit GL. If, for a GL, you have opted for revaluation split, then Revaluation Profit (as opposed to Trading Profit) is posted into this GL.

Revaluation split segregates revaluation profit / loss into:

- | Trading Profit / Loss – Profit / Loss due to revaluation of FCY entries posted into the GL during the current day.
- | Revaluation Profit / Loss – Profit / Loss due to revaluation of opening FCY balances (excludes current day's turnover).

Loss General Ledger

If the result of revaluation is a loss, the loss amount is debited to this loss GL. If, for a GL, you have opted for revaluation split, then Revaluation Loss (as opposed to Trading Loss) is posted into this GL.

Revalue into

This GL account is debited if the result of revaluation is a profit; and credited if the result of revaluation is a loss

This would typically be the GL code being revalued. For all non-contingent GLs belonging to the asset or liability categories, the system defaults to the GL being revalued.

If you wish to specify a different account for posting these entries specify by selecting from the list of maintained GLs. A list of all GLs would be displayed. Select.

Trading Profit Account/Trading Loss Account

This indicates the GL for posting profit/loss due to trading revaluation (Trading Profit / Loss) if you have indicated that revaluation split is required for a GL.

Netting of offset entries

A check against this indicates whether the offset entries for all accounts linked to the GL code need to be netted or not. If checked, a single consolidated entry would be passed (one for profit and one for loss).

Note

Netting of offset entries is applicable only for normal account revaluation and not for accounting entry-based revaluation of Income/Expense GLs.

Accounting entry-based revaluation of Income / Expense GLs

Income/expense GLs that are marked for entry-based revaluation are picked up by the EOD revaluation batch process, which executes before the account revaluation batch process on a given business day.

In the Account Revaluation Maintenance, you must specify the following parameters that would be used by the batch revaluation process, for revaluing FCY entries in Income/Expense GLs:

- I Rate type
- I Transaction code for posting entry-based revaluation entries

You can maintain these parameters for specific Income/Expense GLs. If you wish to maintain these parameters for all Income/Expense GLs, you can specify the 'STDPNL' option in the GL Code field. The 'STDPNL' option signifies that the entry-based parameters being maintained are applicable for all Income/Expense GLs.

When the revaluation batch revalues an Income/Expense GL, it uses the rate type and transaction code maintained for the GL in the Account Revaluation screen. If no maintenance exists for the specific GL, the parameters maintained for the 'STDPNL' GL Code option are used.

20. Maintaining Branch Holidays

20.1 Introduction

For a year, you need to define your weekly holidays and your calendar year annual holidays. This is done in the 'Local Holiday Calendar' screen.

The system uses the information maintained in this screen to do the following:

- To check that the 'value date' of no Data Entry transaction falls on a holiday
- To check that the start date / maturing date and schedule date of a loans and deposit contract does not fall on a holiday
- To effect a date change on the system -- today's date and the next working date

For any schedule / contract maturing at a future date, say, 5 years hence, you can input a future date, only if the calendar for that year has been maintained. It is not necessary to maintain the list of all annual holidays, for future, you can merely define all regular weekly holidays.

This screen is maintained for each branch, of your bank, from the respective branches; thus making it possible to have a different set of holidays for different branches of the bank.

20.2 Invoking Local Holiday Screen

Invoke the 'Local Holiday Calendar' screen, by typing 'STDLOCHL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Local Holiday Calendar Maintenance

New Enter Query

S M T W Th F Sa S M T W Th F Sa S M T W Th F Sa

January February March

April May June

July August September

October November December

Branch * Year * < 1 10 GREATER THAN Refresh

Local Holidays

1 Of 1

| Branch Code | Year | Month | Holiday List |
|-------------|------|-------|--------------|
|-------------|------|-------|--------------|

Fields

Maker Date Time: Mod No
Checker Date Time: Record Status
Authorization Status

Exit

In this screen you can specify the weekly and also the annual holidays, for your branch, for any year between 1 AD and 4000 AD.

20.2.1 Steps to Define Yearly Holidays

To define holidays for a year, (for instance, for 2000) you have to do the following:

Building the calendar for the year

Step 1

Select 'New' from the Actions menu in the Application tool bar or click new icon

Step 2

Enter the year -- 2000 or move to the year 2000 using the arrows

Step 3

To build the calendar for the year, 2000 click the 'Refresh' button. This button is called the 'refresh / build up' button because it builds the calendar for you. Please note:

- On invoking the calendar of any year, you will notice that Saturdays and Sundays are marked as weekly holidays. This is the default setting of the system
- For identification, the working days are marked in black and the holidays in red

- All unauthorised records appear against a blue background. On authorisation of that record, the background is cleared.

20.2.2 Defining Holidays

To define any other weekly holiday, other than the default, double click the day of the week, listed on the top row of the screen. For instance, if you double click on 'F', all Fridays in the year would be marked as holidays.

To clear off the default weekly holidays — Saturdays and Sundays, double click on 'sa' and 's' written on the top row.

To specify, other annual holidays, double click on the date — the date would be marked as a holiday.

If you want to unmark a day specified earlier as a holiday, double click on it, once again. You will notice that the day gets marked in black. Because the change is yet unauthorised, it appears against a blue background.

20.2.3 Annual Holidays

These are the holidays you have defined for the year calendar on display

You will observe that all holidays are marked in red, while working days in black. (All unauthorised holiday dates appear against a blue background). To mark a date as a holiday, double click on it. In case you wish to undo a date marked off as a holiday, double click on it once again. It changes back to a working day.

With each modification you make, the Modification Number in the made by column below moves up serially

20.2.4 Designating Unexpected Holidays for Branch

The holiday calendar for your branch is maintained in the Branch Holiday Calendar screen.

In addition to the holiday calendar, you may need to designate certain days as holidays unexpectedly, without forewarning. Alternatively, you may also need to roll back a previously defined holiday date or set of dates. You can do this using the 'Unexpected Branch Holiday Maintenance' screen. You can invoke this screen by typing 'CGDUNHOL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Unexpected Branch Holiday Maintenance

New Enter Query

Branch Code *
Branch Name

Holiday/Working Type ☒ Holiday ☐ Working

Holiday Date From *
Holiday Date To *
Holiday Reason

Type Exceptions

| Holiday/Working Date | Reversed Flag |
|----------------------|--------------------------|
| | <input type="checkbox"/> |

Fields

Input By Date Time Authorized By Date Time Modification Number

☐ Authorized ☐ Open

In this screen, for the current branch, you can maintain a range of dates, every date within which will be designated as holidays for the branch. You can also provide a reason for the designation.

Every unexpected holiday you designate must be authorized for it to be effective

20.2.4.1 Reversing Designated Holiday

In the Unexpected Holiday Maintenance screen, you can also reverse a designated holiday before the actual date. Specify the holiday date in the Holiday Date field, and check the Reverse box field alongside it.

When you designate unexpected holidays, any bank or customer value dates for any transactions, that coincided with the holiday are rolled forward. Any accounting entries passed are reversed and fresh entries are passed to reflect the new value date.

Note

For the release of uncollected funds, the original transaction date is considered for availability calculations

20.2.4.2 Propagating Local Holidays

Oracle FLEXCUBE facilitates propagation of holiday details maintained in the head branch to all other active branches. This propagation is based on the value maintained for the CSTB parameter 'PROPOGATION_OF_LOH'.

The system defaults the value as 'N' for 'PROPOGATION_OF_LOH', indicating that no propagation is allowed for local holidays; however, you can set the value as 'Y' if you need to allow propagation of holidays.

If the 'PROPOGATION_OF_LOH' value is maintained as 'Y', then the system will enable propagation of holiday maintenance from Head branch to other active branches under the following condition:

- Holiday details are authorized.
- Holiday details are not maintained for the year for the active branches
- Only when the new holiday details are maintained and authorized for the first time. Propagation of holiday maintenance at HO will be allowed for Un-authorized branch also, subsequent modification after first authorization, if year is not maintained for the branch.
- When a new branch is created and authorized for the first time
- Un-authorized branch with modifications after first authorization and no holiday details maintained for the year
- For the branches which are restricted

Propagated records will have the Maker ID and Checker ID details of the HO.

Propagation of Holidays during Modify Operation

After maintaining 'PROPOGATION_OF_LOH' flag as 'Y', if propagation of holidays during modify operation is required, then the parameter 'PROPOGATION_OF_LOH_ON_MODIFY' should also be set as 'Y' in CSTB_PARAM.

In this scenario when both parameters are set as 'Y', the propagation of holidays will also happen during modification of head office record and the calendar for all branches will be overwritten by the Head Office calendar.

21. Maintaining Currency Holidays

21.1 Introduction

You need to maintain a yearly list of holidays, for the currencies, defined in the currency screen. This is done in the 'Currency Holiday Calendar' screen.

The system uses the information maintained in this screen to check whether any settlement, involving a foreign currency (in the foreign Exchange, Money market, Funds Transfer, Loans & Deposit modules) falls on that currency's holiday. If yes, then the system will display a message stating so, and ask the user for an override

For any schedule or contract maturing at a future date say, 5 years hence, you can input the future date, only if the calendar for that year has been maintained.

The currency holiday screen is maintained at the Bank Level by the Head Office

21.2 Invoking Currency Holiday Screen

You can invoke this screen by typing 'STDCCHOL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Currency Holiday Calendar Maintenance

New Enter Query

S M T W Th F Sa S M T W Th F Sa S M T W Th F Sa

January February March

April May June

July August September

October November December

Currency Code * Year * Refresh

Currency Holidays

| Currency | Year | Month | Holiday List |
|----------|------|-------|--------------|
|----------|------|-------|--------------|

Fields

Input By Date Time Authorized By Date Time Modification Number Authorized Open

In this screen, you can maintain a list of holidays for each of the currencies maintained in the 'currency screen', for any year between 1 AD and 4000 AD.

21.2.1 Steps to Define Currency Holidays

To define currency holidays for a year, (for instance, for 2000) you have to do the following:

Building the calendar for the year

Step 1

Select 'new' from the Actions menu in the Application tool bar or click new icon. A blank screen appears and the cursor moves to the field 'Year'

Step 2

Enter the year -- 2000 or move to the year 2000 using the arrows

Step 3

To build the calendar for the year, 2000 click on the 'Refresh' button. This button is called the 'refresh / build up' button because it builds the calendar for you

Step 4

Select the currency for which you are defining holidays. Please note:

- On invoking the calendar of any year, you will notice that Saturdays and Sundays are marked as weekly holidays for the currency. This is the default setting of the system.
- For identification, the working days are marked in black and the holidays in red.
- All unauthorised records appear against a blue background. On authorisation of that record the background disappears.

21.2.2 Defining Currency Holidays

To define any other weekly holiday for the currency, other than the default, double click the day of the week, listed on the top row of the screen. For instance, if you double click 'F', all Fridays in the year would be marked as holidays.

To clear off the default weekly holidays — Saturdays and Sundays, double click on 'sa' and 's' written on the top row


To specify, other holidays, double click on that date — the date would be marked as a holiday

If you want to unmark a day specified earlier as a holiday, double click on it, once again. You will notice that the day gets marked in black. Because the change is yet unauthorised, it appears against a blue background

21.3 Uploading Holiday File

SWIFT provides a country-wise holiday file that can be uploaded into Oracle FLEXCUBE. For all countries where 'EUR' is not the local currency, the respective holidays can be uploaded into the currency holidays tables. For European countries, where 'EUR' is the currency, you can upload the TARGET holidays. Oracle FLEXCUBE allows you to upload these currency holidays through the 'BIC/BICPLUS – Upload' screen. You can invoke this screen by typing

'ISDBICPU' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



The screenshot shows a web application window titled 'BIC Upload'. The window has a dark blue header bar with a diamond icon and the title. Below the header, there is a toolbar with two buttons: 'New' (with a document icon) and 'Enter Query' (with a magnifying glass icon). The main content area is white and contains four input fields: 'Source Code *' (a dropdown menu), 'File Name *' (a text box), 'File Path *' (a text box), and 'Intraday Sequence Number' (a text box). Below these fields are two buttons: 'Submit Parameters' and 'Submit Batch'. The window has a standard Windows-style title bar with minimize, maximize, and close buttons.

Here you need to choose the source code as 'CCH' from the drop-down list. For further details about this screen, refer the section titled 'Uploading the BIC/BICPLUS files into Oracle FLEXCUBE' in the 'Settlements' User Manual.

The holiday file gets uploaded with two records:

- HF Record – wherein 'EUR' is not the local currency
- HS Record - wherein 'EUR' is the local currency

For more details on the file formats of these records, refer the chapter titled 'Annexure – B – File Formats'.

22. Maintaining Clearing Holidays

22.1 Introduction

You need to maintain a yearly list of holidays of your Clearing House. This is defined in the 'Clearing House Holiday Calendar' screen.

This set of holidays is maintained at the bank level, by the Head Office. You can invoke this screen by typing 'STDCLHOL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Clearing House Holiday Maintenance' application window. It features a grid of 12 monthly calendars (January to December) for maintaining holidays. Each month has a header with day abbreviations (S, M, T, W, Th, F, Sa) and a grid of days. Below the calendars, there are input fields for 'Clearing House *' and 'Year *', and a 'Populate' button. At the bottom, there is a 'Holiday Details' section with a list box and a 'Fields' section with checkboxes for 'Input By', 'Authorized By', 'Modification Number', 'Authorized', and 'Open'.

In this screen, you maintain a list of holidays of the Clearing House with which your bank is associated with.

22.1.1 Steps to Define Clearing House Holidays

To define Clearing House holidays for a year, (for instance, for 2000) you have to do the following:

Building the calendar for the year

Step 1

Click new icon.

Step 2

Enter the year — 2000 or move to the year 2000 using the arrows.

Step 3

To build the calendar for the year, 2000 click the 'Refresh' button. This button is called the 'refresh / build up' button because it builds the calendar for you. Please note:

- | Your clearing house can be identified with the name -- SYS, given to it by the Oracle FLEXCUBE system. This is displayed in the field 'Clearing House'
- | Saturdays and Sundays are marked as weekly holidays for the Clearing House. This is the default setting of the system
- | For identification, the working days are marked in black and the holidays in red
- | All unauthorised records appear against a blue background. On authorisation of that record the background disappears

22.1.2 Defining Clearing House Holidays

To define an additional holiday, click the particular date which you need to be considered as holiday. The system will mark that date as a holiday. The system will change the color of the date to red.

If you click a date that is already marked as a holiday, the system will clear the holiday and treat that date as a working day. The color of the date text is changed to black, indicating that it is no more a holiday.

22.1.3 Designating Unexpected Holidays for Clearing House

The holiday calendar for your clearing house is maintained in the Clearing House Holiday Calendar screen

In addition to the holiday calendar, you may need to designate certain days as holidays unexpectedly, without forewarning. Alternatively, you may also need to roll back a previously defined holiday date or set of dates. You can do this using the 'Unexpected Holiday Maintenance' screen.

You can invoke this screen by typing 'CGDCLHOL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

In this screen, for a clearing house, you can maintain a range of dates, every date within which will be designated as holidays for the clearing house. You can also provide a reason for the designation.

Every unexpected holiday you designate must be authorized for it to be effective

22.1.3.1 Reversing Designated Holiday

In the Unexpected Holiday Maintenance screen, you can also reverse a designated holiday before the actual date. Specify the holiday date in the Holiday Date field, and check the Reverse box field alongside it.

When you designate unexpected holidays, any bank or customer value dates for clearing transactions, that coincided with the holiday are rolled forward. Any accounting entries passed are reversed and fresh entries are passed to reflect the new value date.

Note

For the release of uncollected funds, the original transaction date is considered for availability calculations.

23. Document Maintenance

23.1 Introduction

Before opening an account, the customers are expected to furnish the documents to the bank.

The following sections in this chapter discusses about the type of document to be submitted and the document checklist to be maintained.

23.2 Maintaining Document Type

You can maintain the various document types in the 'Document Type Maintenance' screen. To invoke this screen, type 'CSDDOCTY' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

The screenshot shows the 'Document Maintenance' application window. It features a toolbar with 'New' and 'Enter Query' buttons. Below the toolbar, there are input fields for 'Document Category *' and 'Document Description'. A 'Document Type' section contains a table with columns 'Document Type *' and 'Document Type Description'. The table has one row with empty input fields. At the bottom, there are fields for 'Maker', 'Checker', 'Mod No', 'Date Time', 'Record Status', and 'Authorization Status'. 'Ok' and 'Exit' buttons are in the bottom right corner.

Specify the following details:

Document Category

Specify the document category. The adjoining option list displays all the document categories that are maintained in the system. You can select the appropriate one.

Document Type

Specify the type of document.

Document Description

Specify a brief description for the document.

23.3 Viewing Document Type Details

You can view the document type details in the 'Document Type Summary' screen. To invoke this screen, type 'CSSDOCTY' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

The screen is as shown below:

The screenshot shows a web application window titled "Document Maintenance". At the top, there are two buttons: "Advanced Search" (with a magnifying glass icon) and "Reset" (with a circular arrow icon). Below these are two search criteria: "Authorization Status" with a dropdown menu and "Record Status" with a dropdown menu. Underneath is a "Document Category" field with a text input and a small icon. A pagination bar shows "Records per page" set to 15, "1 Of 1" records, and a "Go" button. Below the pagination bar is a table with the following columns: a checkbox, "Authorization Status", "Record Status", "Document Category", and "Document Description". The table contains one row of data. At the bottom right of the window is an "Exit" button.

| | Authorization Status | Record Status | Document Category | Document Description |
|--------------------------|----------------------|---------------|-------------------|----------------------|
| <input type="checkbox"/> | | | | |

You can query on records based on any one or all of the following criteria:

- | Authorization Status
- | Record Status
- | Document Type
- | Document Category
- | Document Description

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- | Authorization Status
- | Record Status
- | Document Type
- | Document Category
- | Document Description

23.4 Maintaining Document Checklist Details

You can maintain the various document checklist details in the 'Document Checklist Maintenance' screen. To invoke this screen, type 'CSDDOCHK' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

The screenshot shows a window titled "Document Reference" with a toolbar containing "New" and "Enter Query" buttons. Below the toolbar are two input fields: "Process Code *" and "Stage *". A section titled "Document Details" contains a table with the following columns: "Document Category *", "Type *", and "Mandatory". The table has one row with a dropdown menu for "Document Category *", a text input for "Type *", and a dropdown menu for "Mandatory" showing "Mandatory". Below the table is a footer section with labels: "Maker", "Checker", "Mod No", "Date Time:", "Date Time:", "Record Status", and "Authorization Status". An "Exit" button is located in the bottom right corner.

Specify the following details:

Process Code

Specify the process code. The adjoining option list displays the process codes that are maintained in the system. You can select the appropriate one.

Stage

Specify the stage in which you need to maintain the checklist details.

Document Category

Specify the document category. The adjoining option list displays all the document categories that are maintained in the system. You can select the appropriate one.

Document Type

Specify the type of document.

Mandatory

Indicates whether the document is needed for checklist.

23.5 Viewing Document Type Details

You can view the document type details in the 'Document Checklist Summary' screen. To invoke this screen, type 'CSSDOCHK' in the field at the top right corner of the Application toolbar and click the adjoining arrow button.

The screenshot shows a web application window titled 'Summary'. At the top, there are buttons for 'Advanced Search' and 'Reset'. Below these are four search filters: 'Authorization Status' (a dropdown menu), 'Record Status' (a dropdown menu), 'Process Code' (a text input field with a search icon), and 'Stage' (a text input field with a search icon). Below the filters is a pagination bar showing 'Records per page' set to 15, and '1 Of 1' records. Below the pagination bar is a table with five columns: 'Authorization Status', 'Record Status', 'Process Code', and 'Stage'. The table has several rows, each with a checkbox on the left. At the bottom right of the window is an 'Exit' button.

You can query on records based on any one or all of the following criteria:

- | Authorization Status
- | Record Status
- | Process Code
- | Stage

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- | Authorization Status
- | Record Status
- | Process Code
- | Stage

24. Configuring Overrides

24.1 Introduction

The system displays messages in respect of errors that occur when you execute operations during a work session, in any module. These error messages are also displayed in respect of automatic or batch processes, such as end of day processes.

Depending upon your requirements at your installation, you might require some of the errors to be ignored, and others to result in an override being sought from the user for the operation to proceed. For still others, you might require an online authorization for the operation to proceed. Accordingly, the implementers at your installation configure the sensitivity of such errors. Subsequently, you might also need to configure errors to suit your requirements.

24.1.1 Types of Overrides

In Oracle FLEXCUBE, you can assign a level of sensitivity to each override that arises or occurs during system operation. This level of sensitivity that you assign to an override indicates the action that will result when that specific override occurs. Accordingly, you can assign any of the following sensitivity levels to an override:

Ignore

This would mean that no override message would be displayed and the exception would be ignored

Override

This sensitivity indicates that an override message should be displayed, seeking confirmation from the user. If the user confirms or accepts the override, processing of the transaction would proceed; if not, the exception would have to be corrected before transaction processing can proceed.

For such overrides, you can assign an additional parameter to indicate whether an online authorization is required if the override is accepted. If you have assigned online authorization to be required, then, for transactions involving such overrides, an online authorization is requested as a mandatory procedure. The online authorization limit specified for the authorizer would be checked during authorization, in addition to the time level of the authorizer, which should be greater than the user who is input the transaction.

For such overrides, if you have specified that no online authorization is required, the user can accept the override, and it will not require any online authorization.

Error

This would indicate that, when an exception occurs, an override message would be displayed, and the transaction cannot be processed further, that is, it would stop being processed until the exception is corrected.

Online Authorization

This would indicate that an override message would be displayed, seeking confirmation from the user. However, in this case, online authorization would be required as a mandatory procedure, if the override were accepted.

Dual Authorization

This would indicate that an override message would be displayed, seeking confirmation from the user. However, in this case, online authorization would be required as a mandatory procedure, if the override were accepted. Also, at least two authorizers would be needed to authorize the transaction.

Override Types for Batch Functions

For exceptions occurring during execution of automatic or batch processes, you can assign the Ignore, Override or Error sensitivities.

24.2 Specifying Override Type

In the 'Overrides Maintenance' screen, all the error messages that would appear in each module, with their respective error codes, are displayed. The functions, with respect to which the error messages could be encountered, are also displayed. You can invoke this screen by typing 'CSDOVDMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Overrides Maintenance' application window. It features a title bar with standard window controls. Below the title bar are two buttons: 'New' and 'Enter Query'. The main area is divided into two sections. The first section, 'Language', contains a 'Language *' text box with a dropdown arrow and a 'Description' text box with a dropdown arrow. The second section, 'Error details', contains an 'Error Code *' text box, a 'Type' dropdown menu currently set to 'Ignore', a 'Function' text box, a 'Message' text box with a dropdown arrow, a 'Confirm' checkbox, a 'Parameters' text box, and a 'Batch Type' dropdown menu currently set to 'Ignore'. At the bottom of the window is a 'Fields | Conversion' tab. Below the tab is a table with three columns: 'Input By', 'Authorized By', and 'Modification Number'. The 'Input By' and 'Authorized By' columns have 'Date Time' as a sub-header. The 'Modification Number' column has 'Number' as a sub-header. Below the table are two checkboxes: 'Authorized' and 'Open'.

In the Type field, you can specify, for each error message, the appropriate sensitivity level – Ignore, Override, Error, Online Authorization or Dual Authorization.

For error messages in respect of automatic or batch functions, you can specify the appropriate level in the Batch Type field – Ignore, Override or Error.

For certain overrides, (to which you have assigned the level Override, Online Authorization or Dual Authorization), you can indicate whether the authorizer must also confirm the override, by checking the Confirm box.

Note

You can make changes to configurable overrides in the Error Codes Maintenance screen only after consulting the support team at your installation.

24.2.1 Maintaining Override Conversion

Click 'Conversion' button on the 'Overrides Maintenance' screen to maintain the conversion error codes for the override error code using 'Overrides Conversion' screen.

You can enter the following details:

Branch Code

Specify the branch code. If ALL is specified, in all the branches the conversion will be done. However if it is maintained for a specific branch, only in that branch the conversion will be done.

Function Id

Specify function Id for which the override should be treated as error.

New Error Code

You can map an already existing error code as the conversion error code or can use the 'Override Maintenance' screen to define the same.

You are not allowed to maintain/map conversion error codes for the error code which is a conversion error-code.

Note

- If you encounter overrides while processing, the system will check if any conversion error code mapped for the override for the combination of branch and function Id. If available then the system will raise the mapped error code instead of the original error code.
 - The system will allow you to map conversion codes only for the error codes with type as 'Override'.
 - If a modifiable error code is changed from 'Override' to 'Error', then the system will delete all the conversion error codes maintained for the same.
-

24.2.2 Maintaining Error Codes

According to the requirements of your bank, you can configure the system to display an error message if you have not opted for batch balancing at the time of opening a batch.

This is indicated in the 'Overrides Maintenance' screen before opening a batch.

You can invoke the 'Overrides Maintenance' screen by typing 'CSDOVDMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Overrides Maintenance' window. It contains fields for Language, Description, Error Code, Type (set to Ignore), Function, Message, Confirm, Parameters, and Batch Type (set to Ignore). The bottom status bar includes Input By Date Time, Authorized By Date Time, Modification Number, and checkboxes for Authorized and Open.

According to your instructions in the 'Overrides Maintenance' screen, Oracle FLEXCUBE will either:

- Display an error message if balancing is not allowed at the time of opening a batch (system will allow you to enter the details of the journal entry only if the option 'Balancing' is checked)
- Display an override message reminding that the batch that has been opened will not be balanced (even if the option 'Balancing' is unchecked, system will display an override and allows you to proceed further and enter the journal entry details)
- Ignore your selection for the option 'Balancing'. System will not display an error message or override irrespective of your selection for the option 'Balancing' and you can proceed to enter the details of the journal entry in the 'Journal Entry' screen.

According to the requirements of your bank, indicate your option (Error, Override, or Ignore) for the error code DEBATBAL-1.

Depending on your selection in the 'Overrides Maintenance' screen for the error code DEBATBAL-1, system will either display an error message or an override message or will just ignore your selection for the option 'Balancing'.

In the 'Overrides Maintenance' screen, if you have indicated the 'Type' as 'Error' and if you don't opt for 'Balancing, system will display an error message as "The batch is not balanced".

and 'Balancing' is automatically checked. In other words, it is mandatory to opt for balancing. This is to ensure that all batches that are opened to post entries are balanced.

If you have indicated the Type as 'Override' and you haven't checked the option 'Balancing' system will display an override message as "The batch is not balanced. Do you want to proceed? Yes/No".

You can proceed to enter the details of the journal transaction if you select 'Yes'.

If you have opted for 'Ignore' in the 'Error Codes Maintenance' screen, irrespective of whether you opt for balancing of batches or not, system will allow you enter the details of the journal transaction in the 'Journal Entry' screen (system will not display an error message or an override).


25. Maintaining Features

25.1 Introduction

In order to improve the performance of the system during online or batch processes, you can install some features on need basis on the system. This chapter explains the process of installing features.

25.2 Maintaining Feature ID

You can maintain required features using the 'Feature ID Maintenance' screen. You can invoke this screen by typing 'CSDFEAMT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



You can specify the following details:

Branch Code

Specify the branch where the feature needs to be installed. The adjoining option list displays all valid branch codes maintained in the system. You can select the appropriate one.

Branch Name

The branch name is displayed here based on the chosen branch code.

Feature Id

Specify the feature that should be installed in the branch. You can also choose any of the following values from the adjoining option list:

| Feature Id | Description | Mode - Online/Batch |
|------------|-------------|---------------------|
|------------|-------------|---------------------|

| | | |
|--------------|----------------------------------------------------------------------------------------------------------|--------------|
| ACCRESTR | Account Restriction feature which need to be enabled for replace amounts in overrides with wild char (*) | Online |
| ACSTHAND | Account Statement Handoff during EOD | Batch |
| APY | Movement of Annual Percentage Yield to history | Batch |
| CCYPOS | CCY position entries updation during EOD | Batch |
| CUSTMIS | building of Customer MIS details Transaction/Composite/Fund | Online |
| DDRECLOG | During Demand Draft creation - update of record log and field log | Online |
| DEFERLIQ | IC Deferred Liquidation | Batch |
| DORMUPD | Dormancy update during EOD | Batch |
| DRINTDUE | Dr. Interest Due | Batch |
| FCTDSTATS | Financial cycle wise account statistics update | Batch |
| GLCUSTSTATS | Period/Financial cycle wise customer GLs statistics update | Batch |
| GLFCTDSTATS | Financial cycle wise GL statistics update | Batch |
| GLPTDSTATS | Period wise GL statistics | Batch |
| ICINTSTMT | IC Interest Statement generation | Batch |
| ICRATECHG | Rate change Advice | Batch |
| IRASTMT | IRA Statement generation during EOD | Batch |
| LDSTMT | Loan Statements generation during EOD | Batch |
| LINKSTMTAC | Update of Previous Statement Date and No during statement generation | Batch |
| PRODTXNREST | Product and Transaction code restrictions applicability | Batch |
| PTDSTATS | Period wise account statistics update | Batch |
| RAC | Account entry serial number derivation logic when multiple FCUBS instances exists | Online/Batch |
| REGCC | Regulatory CC update for customer account during EOD | Batch |
| TRACKACCRINT | Tracking of Accrued interest | Batch |
| USREGCHGS | US Regulatory changes | Batch |

| | | |
|-----------|------------------------------------------------------------------------|--------|
| VDBALINIC | VD balance update. This is equivalent to flag at bank parameters level | Online |
|-----------|------------------------------------------------------------------------|--------|

Installed

Check this box to indicate that the feature should be installed in the branch.

Click save icon in the Application tool bar to save the changes.

25.2.1 Specifying UDF Values

All User Defined Fields (UDFs) linked to the function ID 'CSDFEAMT' are displayed in the 'User Defined Fields' screen. Invoke this screen by clicking 'Fields' button on the 'Feature ID Maintenance' screen.

The screen is as shown below:

Here you can specify values for each UDF.

Refer the User Manual titled 'User Defined Field' for details about defining UDFs.

25.3 Viewing Feature ID Summary

You can view summary of all feature IDs installed across branches, using the 'Feature ID Summary' screen. To invoke this screen, type 'CSSFEAMT' in the field at the top right corner of the Application tool bar and click the adjoining arrow button.

The screen is as shown below:

The screenshot shows a web application window titled 'Summary'. At the top, there are buttons for 'Advanced Search' and 'Reset'. Below these are search filters: 'Authorization Status' (a dropdown menu), 'Record Status' (a dropdown menu), 'Branch Code' (a text input with a search icon), and 'Feature Id' (a text input with a search icon). There is also a checkbox labeled 'Installed'. Below the filters is a pagination bar showing 'Records per page' set to 15, with buttons for 'First', 'Previous', '1 Of 1', 'Next', 'Last', and a 'Go' button. Below the pagination bar is a table with the following headers: 'Authorization Status', 'Record Status', 'Branch Code', 'Feature Id', and 'Installed'. The table body is currently empty. At the bottom of the window, there are buttons for 'Authoriza' (partially visible), 'Record St' (partially visible), and 'Exit'.

You can query on records based on any one or all of the following criteria:

- | Authorization Status
- | Record Status
- | Branch Code
- | Feature ID
- | Installed

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- | Authorization Status
- | Record Status
- | Branch Code
- | Feature ID
- | Installed

Double click on a record to invoke the detailed screen for that record.

26. Purging Data

26.1 Introduction

Purging is a process by which you remove unwanted data from the system. For example, you may find the interest rates that you have maintained for a financial cycle useless a couple of years later. You would want to remove such data from the system. You can achieve this by 'purging' the data of the system.

There are two types of purging data:

- Module Purging
- Entity Purging (User Defined)

26.2 Module Purging

The purge function of Oracle FLEXCUBE allows you to purge:

- Contracts and transactions that you have entered into,
- Data relating to transactions (such as, interest rates)
- Limits history (Liability, Lines and Line Utilization history)
- GL Average Balance and Customer Account statistics

You can purge the contracts (or transactions) that you have entered into in the following modules of Oracle FLEXCUBE:

- Foreign Exchange
- Money Market
- Loans
- Deposits
- Data Entry
- Standing Instructions
- Letters of Credit
- Bills and Collections


You can purge data from the following modules:

- Accounting
- Currency
- General Ledger
- Interest and Charges
- Messaging
- MIS
- Reconciliation
- Receivable Liquidation

You can also purge data relating to transactions. For example, you can purge the currency rates that you have maintained, the messages in the messaging system of Oracle FLEXCUBE, the User Data Elements that you used to compute interest, interest statement details, user information maintained in the Security Management System of Oracle FLEXCUBE, customer information, and so on.

26.3 The system will automatically purge data according to the parameters that you define in the Purge Details Maintenance screen. **Maintaining Purge Details**

In the 'Purge Details Maintenance' screen, you can define the parameters for purging data from the system. For instance, you may want to purge the contracts entered into in the previous financial cycle. Or, you may want to retain exchange rates in the system for a specific period. These are examples of parameters that you can define in the Purge Details Maintenance screen. You can invoke this screen by typing 'CSDPURGE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



26.3.0.1 Specifying Module

In the Purge Details Maintenance screen you must first specify the module for which you are defining parameters. All parameters that you define subsequently will only apply to the module that you specify.

You can enter a description of the module for which you are maintaining purge details.

Note

For purging limits history which is Liability, Lines, and Lines Utilization history, you must specify LM as the module code. Limits history data is purged for the current branch only.

26.3.0.2 Specifying Nature of Data to be Purged

You can opt to purge contracts (of the module you specified) along the following criteria. You may either choose to purge any of the following:

- Liquidated contracts
- Closed (applicable only to the BC and LC modules)
- Reversed contracts

When you run the purge process, only those contracts that are in the status that you specified will be purged. That is, only contracts (in the module you specified) that are liquidated, closed, and/or reversed, depending on your specification, will be purged from the system.

Similarly, if you want to purge

- Exchange rates (from the Currency module), you should choose the 'None' option.
- Data from the Reconciliation module, you should choose any of the following options, depending on the data that you want to purge. The options available are:
 - System Date Relative
 - Match Relative
 - Closed Match
 - Closed External Statement

Retention Period

The retention period, as the term suggests, is the period for which data is stored in the system. For each module in Oracle FLEXCUBE, you can specify the retention period.

When you run the purge process on any given day, only the data that is beyond the retention period that you specified will be purged. The following example illustrates this concept.

For example,

The requirement: You would like to retain foreign exchange contracts that were liquidated 60 days prior to the running of the purge process, in the system. (That is, if the current system date is 30 June 1999 and you do not wish to purge the foreign exchange contracts that were liquidated between 1 May 1999 and 30 June 1999).

Solution: In the Retention Period field enter '60' (note this value is expressed in days), and in the 'Status' field choose the 'Liquidated' option.

Result: If this setup is authorised, and you run the purge process on 30 June 1999, the current system date, all foreign exchange contracts that you liquidated prior to 1 May 1999 will be purged. Contracts that were liquidated on or after 1 May 1999 will not be purged.

26.4 Entity Purging

In entity purging, you can archive or purge the data from the main tables and its child tables. You can also configure the purge type and the frequency of data purging.

There are 3 parts in an entity purging:

Purge Parameter Definition

The purge parameter definition is achieved through ODT. The ODT generates the purge source files which is then deployed in Oracle FLEXCUBE.

The ODT is used for the following:

- Maintaining the list of entities that need to be purged.
- Maintaining the purge behaviour.
- Maintaining the mode of purge.
- Maintaining the purge frequency.
- Maintaining the archive table suffix if the purge behaviour is to archive the data.
- Maintaining the filter criteria to determine what data to purge.

You can capture the above parameters to define the entity and purge preferences.

Purge Parameter Configuration

Once the ODT generated scripts are deployed in Oracle FLEXCUBE, they can be re-configured in the purge parameter configuration.

Purge Execution

You can execute the purge in two modes:

- Batch Mode - In the batch mode you have to maintain the purge entity batch CSBPURGE. The AEOD batch process starts the purge process in which all the entities that are scheduled for purge on that day gets purged.
- Ad-hoc Mode - This mode supports purging of a single entity at any time.

You can define entities for purging in any module. However, pre-defined entities are available for the following modules:

- Accounting
- Bills and Collections
- Letters of Credit
- Funds Transfer
- SWITCH

26.4.1 Configuring Purge Parameters

You can configure the parameters for purging the data through 'Purge Parameter Configuration Maintenance' screen. You can query and modify entities in this screen. However new operation is not allowed. To invoke this screen type 'STDPGMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Purge Parameter Configuration' window. At the top, there's a title bar with a diamond icon and the text 'Purge Parameter Configuration'. Below the title bar is a toolbar with a magnifying glass icon and the text 'Enter Query'. The main area contains a form with the following fields: 'Entity Id' (with a red asterisk), 'Purge Frequency' (a dropdown menu set to 'Daily'), 'Next Purge Date', 'Commit Frequency' (set to '100'), 'Description', 'Last Purge Date', and 'Query'. Below the form is a table with the following columns: 'Filter Name', 'Column Data Type', 'Left Hand Side', 'Operator', and 'Right Hand Side' (with a red asterisk). The bottom of the window has a 'Branch Restriction' section with fields for 'Maker', 'Checker', 'Mod No', 'Date Time', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

The following details are captured in this screen:

Entity Id

Select the entity Id from the adjoining option list.

Purge Frequency

Select the frequency of purge from the adjoining drop-down list. The available options are:

- Ad-hoc - If the frequency is selected as Adhoc, then this particular entity will not be picked up for purging in the batch purge. This entity can be purged only by the Adhoc Purge option.
- Daily - The purge routine for the entity having daily frequency will run daily
- Weekly - The purge routine for the entity having weekly frequency will run every week. The day of the week will be determined based on the purge start date. If the purge start day is a Monday, then the purge routine runs on every Monday. If you want to change the day of the week, then 'Next Purge Date' needs to be updated.
- Monthly - The purge routine for the entity having monthly frequency will run every month. It is advised that the purge routines are not configured during the month-ends, as Purge Anniversary dates so as to reduce the processing load on the month-ends
- Quarterly - The purge routine for the entity having quarterly frequency will run every quarter.
- Half-Yearly - The purge routine for the entity having half-yearly frequency will run every 6 months.
- Yearly - The purge routine for the entity having yearly frequency will run every year.

Last Purge Date

The system displays the date on which the entity is purged.

Next Purge Date

Specify the next date for purging the entity. The system populates this date if purge frequency is not ad-hoc.

The next purge date is left blank initially. The system picks up for automatic purging of data and updates the subsequent dates only if the next purge date is provided.

Commit Frequency

Specify the commit frequency while purging the data. The default value for commit frequency is 100.

For example,

If the value is 100 (which is default), then the purge routine will commit after every 100 records.

Query

The system displays the full query for the entity.

Filter Details**Filter Name**

The system displays the name of the purge filter criteria.

Column Data Type

The system displays the data type for the filter.

LHS

The system displays the LHS of the filter expression.

Operator

The system displays the operator for the filter.

RHS

The system displays the RHS or the value for the expression based on which data is purged. However RHS can be modified.

Branch Restrictions

Click on 'Branch Restrictions' to allow or disallow entities across branches.

The screenshot shows a 'Branch Restriction' dialog box. It contains a text input field for 'Entity Id'. Below this, there are two radio buttons for 'Branch Restriction': 'Allowed' and 'Disallowed', with 'Disallowed' being selected. A table is displayed below the radio buttons, with a single column header 'Branch Code'. The table is currently empty. At the bottom right of the dialog, there are 'Ok' and 'Exit' buttons.

Entity Id

The system displays the entity ID.

Branch Restriction

Indicate whether the branch restriction is 'Allowed' or 'Disallowed'.

Branch Code

The system displays the branch code. However, you can add the branch codes here.

You should configure the branch restrictions as part of first time entity configurations.

26.4.2 Viewing Purge Parameter Configuration Details

You can view the purge parameter configuration details maintained in the 'Purge Parameter Configuration' screen using the 'Purge Parameter Configuration Summary' screen. You can

invoke this screen by typing 'STSPGMNT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

In the above screen, you can base your queries on any or all of the following parameters and fetch records:

- Authorization Status
- Entity Id
- Record Status

Select any or all of the above parameters for a query and click 'Search' button. The system displays the records meeting the selected criteria:

- Authorization Status
- Record Status
- Entity Id
- Description

26.4.3 Processing Ad-hoc Purge

You can process ad-hoc purge through 'Ad-hoc Purge Process' screen. An entity configured as automatic can also be started from this screen. However, this would not change the regular frequency cycle of the entity. The next purge date is not effected or changed if started from

this screen. To invoke this screen type 'AEDPGOP' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Entity Id

Select the entity ID from the adjoining option list.

Purge Frequency

The system displays the purge frequency.

Number of Threads

The system displays the number of parallel streams in which the purge should be run. However, you can modify it. The purge batch process is split into specified numbers and executed in separate threads.

Description

The system displays description on the entity ID.

Next Purge Date

The system displays the next purge date.

Last Purge Date

The system displays the last purge date.

Query

The system displays the query for the entity.

The system displays the following details:

- Filter Name - Name of the purge filter criteria
- Column Data Type - Data type of the filter
- LHS - LHS of the filter expression
- Operator - The operator for filter
- RHS - RHS or the value for the expression based on which data is purged. However, you can modify this.

Note

- Only 'Execution Filter' conditions are displayed in the Filter Condition Multi Entry Block.
 - 'Business Filter' conditions will not be displayed.
-

26.4.4 Inquiring Purge Log

You can inquire the purge history through the Purge Log Inquiry screen. To invoke this screen type 'AEDPGLOG' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

| Entity Id | Run ID | Date | Start Time | End Time | Status | Error | Number of Records | Query |
|-----------|--------|------|------------|----------|--------|-------|-------------------|-------|
| | | | | | | | | |

Entity Id

Select the entity Id from the adjoining option list.

From Date

Specify the date from when the log should be enquired.

To Date

Specify the date till when the log should be enquired.

The system displays the following details:

- Entity ID
- Run ID
- Date
- Start Time
- End Time
- Status
- Error
- Number of Records
- Query

27. Support 24x7

27.1 Introduction

Oracle FLEXCUBE is available on a 24x7 basis for two broad channels Web service & Web Branch. During EOD batch process, transactions are tanked and then get processed after the batch is completed.

This document details about the 24x7 support feature in FCUBS.

27.1.1 Gateway Messaging

Oracle FLEXCUBE processes the following channel transactions, 24x7:

- FLEXCUBE UBS - Gateway - Web service
 - Customer (New, Modify, Close)
 - Customer Account (New, Modify, Close)
 - Fund Transfer
 - Payment & Collections
 - Consumer Loans

All new requests for maintenance functions or online functions when the branch available status is 'No' are accepted at the Gateway messaging layer. The Gateway messaging layer does not route the transaction requests during the Date Change Window.

27.1.2 Web Branch

Oracle FLEXCUBE processes the following channel transactions, 24x7:

- FLEXCUBE UBS - Retail Web Branch UI
 - Retail Teller
 - Instruments
 - Clearing
 - Utility Payments
 - Retail Loan

27.1.3 Batch Processing

Every day while processing a channel transaction, system checks for the branch availability status. The system displays the Branch Available status. If the status is 'Yes', it indicates that the branch can accept transactions for the day and if the status is 'No', then it indicates that the transactions will be accepted but it will be in effect only from the next business day.

Accordingly accounting entries will be passed checking the following, for tanking branch transactions:

- The Branch Available Status
- The Branch date and host date i.e. entries will be tanked if branch date is ahead of host date

When the Branch Available status is 'NO' or if branch date is ahead of host date, then the transactions will be tanked. These transactions will be untanked by the BOD program which runs post date change i.e. POSTDTCH.

The branch available status can be changed from Yes to No in two ways.

- Auto
 - At the start of EOTI if the branch available status is not 'No'.
 - At the start of ICEOD if the branch available status is not 'No'.
 - At the start of EOFI if the branch available status is not 'No'.
 - Drop of End of Transaction Input
 - System Date Change
- Manual
 - Manual – Scheduling and Execution as EOD batch.

IC EOD Process

The account resolution during IC EOD process excludes accounts that are with account creation status as Tanked.

Drop - End of Transaction Input (EOTI)

If the branch is not available during the Drop End Of Transaction Input, system automatically resets the Branch available status to 'Yes'. Also all the tanked transactions and accounting entries are released.

All transactions that are tanked would be released with tanked status as No and advices and payment messages if suppressed would be generated.

For the process that started when the branch available status was Yes, then the Status change to 'No' cannot be changed till the completion of the process. This is applicable for DE Batch upload process.

27.1.4 Processing Different Categories during EOD

During EOD batch process, the categories like maintenance and financial transaction process are explained below.

27.1.4.1 Processing Maintenance

The maintenance process includes:

- New Customer Creation
- Customer Amendment
- Customer Closure
- New Account Creation
- Account Amendment
- Account Closure

Creating Customers

While creating customer if the branch available status is no, then the creation date gets set to next branch working date. The customer details report requests are accepted and the processing of the same starts only during the next branch available status. The report would include the customer creation date also.

Creating Customer Accounts

The customer account creation requests are processed with the tanked status as 'Yes' if the branch is not available for transaction and these accounts are not considered for Interest & Charges calculation process

After the branch is available after the date change process, tanked status gets changed to 'No' and initiation entries of term deposit that are tanked are released with transaction date moved to next working date.

Processing TD Account Creation

The Term Deposit creation requests are processed with the tanked status as 'Yes' if the branch is not available for transaction. If the customer account is displaying as tanked, it indicates that the customer account creation request was processed when the branch available status is No or when branch date was ahead of host date.

The process when the TD account creation is received when the branch is unavailable or when branch date is ahead of host date is as follows:

- The TD account creation would be accepted with transaction status as Tanked.
- The initiation accounting entries will be posted as tanked entries.

The Term Deposit accounts that are in tanked status will not be considered for Interest & Charges calculation process.

After the branch available status is changed to 'Yes' then:

- The TD account tanked status will set to No.
- The Initiation entries of term deposit that are tanked would be released with transaction date moved to next working date.

Processing TD Account Redemption

The Term Deposit Redemption Transactions are processed partially if the branch is not available for transaction or when branch date is ahead of host date. Partial Redemption of the account is processed even after branch available status is 'No' or branch date is ahead of host date

- For TD redemption by Transfer to Savings, TD redemption by Transfer to GL, the RT Transaction done for moving the available funds will get tanked.
- For TD redemption By Bankers Cheque, the Instrument Transaction done for Issuing the BC will get tanked.

After the branch available status is changed to 'Yes' then:

- The transaction status of the TD Redemption Transaction will be changed to Active.

The tanked accounting entries if any would be un-tanked by the batch process.

Processing Account Closure

The Close out Withdrawal Transaction is not allowed if the branch is not available for transaction or when branch date is ahead of host date.

27.1.4.2 Processing transactions:

The transaction process includes:

- Payments and Collections
- Retail Loan
- Fund Transfer
- Retail Teller
- Instruments
- Standing Instructions
- Clearing

- Utility Payments

Processing Funds Transfer

The fund transfer requests are processed with tanked status if the branch is not available for the transactions assuming that the FT Product cut-off time is maintained such that the cut-off time is past for the FT transaction when the Branch available status is changed to No.

The process when the FT transaction is received when the branch is unavailable is as follows:

- The FT transaction would be accepted with tanked status as Yes.
- There would be no change in the debit & credit value date derivation which currently takes in to consideration the value date spreads and cut-off time maintained in FT - Value Date Spread maintenance.
- There would be no change in the derivation of the following processing dates –
 - Messaging Date
 - Accounting Entry Date
 - Rate Date
- If the Messaging Date of the FT transaction is derived as the application date then the message generation would be suppressed and the message will be generated once the branch available status changes to 'Yes'
- Accounting entries would be posted with tanked status if the accounting date derived is as of the application date.
- Advices associated with FT transaction events if any would be suppressed and generated once the branch available status changes to 'Yes'

After the branch available status is changed to 'Yes' after the business date change then

- The tanked status of the FT transaction would be set to No
- The tanked accounting entries if any would be un-tanked by the existing batch process for releasing the accounting entries.
- Advices of the FT transaction if suppressed would be generated.
- If the payment message generation for FT transaction was suppressed, the same would be generated during the transaction release.

The following FT operation requests when the branch available status is No would be accepted and the processing would be deferred till the branch available status is yes. The requests would be tanked at the FC UBS Gateway messaging layer.

- Cancellation of FT Transaction
- Amendment of FT transaction
- Liquidate FT transaction
- Reversal of FT transaction

Processing Payments and Collection

The PC requests are processed with the tanked status as 'Yes' if the branch is not available for transaction assuming that the PC Product cut-off time is maintained such that the cut-off time is past for the PC transaction when the Branch available status is changed to No.

If the PC request is received past the cut-off time maintained at the product/customer level, the activation date would be moved to next working date with the other processing dates resolved based on the activation date keeping as same. For Debit Liquidation - DRLQ event and Credit Liquidation - CRLQ event dates derived is application date, then the accounting entries are posted with tanked status.

For a book transfer, if the dispatch date derived is the application date then the offset transaction is generated and processed. The offset transaction accounting entries as part of DRLQ event and CRLQ event are posted with tanked status if the accounting entry date derived is the application date. After the branch status is available, then the tanked accounting entries if any would be un-tanked by the existing batch process for releasing the tanked accounting entries.

The following PC operation requests when the branch available status is No would be accepted and the processing would be deferred till the branch available status is yes. The requests would be tanked at the FC UBS Gateway messaging layer.

- Amendment of PC transaction
- Reject/Recall of PC Transaction
- Approval of Incoming collection
- Reversal of PC transaction
- Re-dispatch of Outgoing collection
- PC periodic instruction setup transaction

Processing Retail Teller Transactions

The retail teller transactions are processed with the tanked status as 'Yes' if the branch is not available for transaction. During the RT transaction query, the transaction can be viewed as tanked, if the RT transaction is tanked and that the request was processed when the branch available status is No or when branch date was ahead of host date.

The process when the RT transaction is received when the branch is unavailable or when branch date is ahead of host date is as follows:

- The RT transaction would be accepted with transaction status as Tanked.
- The accounting entries would be posted with tanked status.
- Message and advices of an RT transaction are suppressed.

After the branch available status is changed to 'Yes' then

- The transaction status of the RT transaction will be changed to Active.
- The tanked accounting entries if any would be un-tanked by the batch process for releasing the tanked accounting entries.
- The messages and the advices associated with the RT transaction that were suppressed are also generated.
- The transaction date of the RT transaction will remain unchanged during the process of un-tanking.

Processing Clearing Transactions

The clearing transactions are processed with the tanked status as 'Yes' if the branch is not available for transaction. During the clearing transaction query, the transaction can be viewed as tanked, if the CG transaction is tanked and that the request was processed when the branch available status is No or when branch date was ahead of host date.

The process when the clearing transaction is received when the branch is unavailable or when branch date is ahead of host date is as follows:

- The Clearing transaction would be accepted with transaction status as Tanked.
- The accounting entries would be posted with tanked status.

After the branch available status is changed to 'Yes' then:

- The transaction status of the Clearing transaction will be changed to Active.

- The tanked accounting entries if any would be un-tanked by the batch process for releasing the tanked accounting entries.

Processing Instrument Transactions

The instrument transactions are processed with the tanked status as 'Yes' if the branch is not available for transaction. During the DD transaction query, the transaction can be viewed as tanked, if the DD transaction is tanked and that the request was processed when the branch available status is No or when branch date was ahead of host date.

The process when the instrument transaction is received when the branch is unavailable or when branch date is ahead of host date is as follows:

- The instrument transaction would be accepted with transaction status as Tanked.
- The accounting entries would be posted with tanked status.

After the branch available status is changed to 'Yes' then:

- The transaction status of the Instrument transaction will be changed to Active.
- The tanked accounting entries if any would be un-tanked by the batch process for releasing the tanked accounting entries.

Processing Standing Instructions

The standing instructions are processed with the tanked status as 'Yes' if the branch is not available for transaction. During the standing instruction query, the instruction can be viewed as tanked, if it is tanked and that the request processed when the branch available status is 'No' or when branch date was ahead of host date.

When the instruction is received while the branch is unavailable, then the process is as follows:

- The instruction is accepted with transaction status as 'Tanked'.
- Accounting entries are posted with the status 'Tanked'.

Once the branch status is 'Available', then the following process is applicable:

- The transaction status of the instruction is changed to 'Un-tanked'
- A batch process releases the tanked accounting entries
- For all instructions whose booking date is the same as the Application date, the 'Date Change BOD Batch' of that date updates the status to 'Un-tanked'.
- The transaction date of the instruction remains the same after un-tanking.

Processing Utility Payment Transactions

The utility payment transactions are processed with the tanked status as 'Yes' if the branch is not available for transaction. During the UP transaction Query, the transaction can be viewed as tanked, if the UP transaction is tanked and that the request was processed when the branch available status is No or when branch date was ahead of host date.

The process when the utility transaction is received when the branch is unavailable or when branch date is ahead of host date is as follows:

- The UP transaction would be accepted with transaction status as Tanked.
- The accounting entries would be posted with tanked status.

After the branch available status is changed to 'Yes' then:

- The transaction status of the UP transaction will be changed to Active.
- The tanked accounting entries if any would be un-tanked by the batch process for releasing the tanked accounting entries.

The different categories which get processed during the End of the Day batch run are explained in the table below:

| Maintenance/ Transactions | Branch Status – Not Available | Branch Status – Available (After date change) |
|--------------------------------------|-----------------------------------------------------------------------------------------------------------------------------------------------------|----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Customer/Account Creation | The process is tanked till the branch available sta- tus is yes. Initiation accounting entries will be posted as tanked entries. | TD account status is changed from tanked to un-tanked. Initiation accounting entries are un-tanked and released with transaction date moved to next work- ing date. |
| TD Account Redemption | Processed partially | Transaction status is un- tanked and accounting entries if any would be un-tanked |
| Account Closure | Not Allowed | Processed normally |
| Funds Transfer | Transaction/Accounting entries would be posted with tanked status. | Transaction/Accounting entries are un-tanked and processed. |
| Payments and Col- lection | Transaction/Accounting entries would be posted with tanked status. | Transaction/Accounting entries are un-tanked and processed. |
| Retail Teller Trans- actions | Transaction/Accounting entries would be posted with tanked status. | Transaction/Accounting entries are un-tanked and processed. |
| Clearing Transac- tions | Transaction/Accounting entries would be posted with tanked status. | Transaction/Accounting entries are un-tanked and processed. |
| Instrument Trans- actions | Transaction/Accounting entries would be posted with tanked status. | Transaction/Accounting entries are un-tanked and processed. |
| Utility Payment Transactions | Transaction/Accounting entries would be posted with tanked status. | Transaction/Accounting entries are un-tanked and processed. |

28. Tanking of Maintenance Records

28.1 Introduction

The maintenance records that are created or modified in the system can be tanked till they get authorized, so that it is possible to undo the modifications, if needed, before the records are authorized. The maintenance log also will store the changes till they get authorized. The new or the modified records are written to the static tables only after authorization.

28.2 Tanking New and Modified Maintenance Records

You can enable tanking of the creation and modification of maintenance records by selecting the 'Tanking Required' option provided at the function Id level. You need to enable the 'Tanking Required' option in RAD tool as well.

You can enable 'Tanking Required' option for individual function Ids in 'Function Description Maintenance' screen. You can invoke this screen by typing 'SMDFNDSC' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows the 'Function Description' screen. The top section contains input fields for 'Function Id', 'Module List', 'User Function Id', 'Name', 'Type' (set to 'Form'), and 'Menu Head' (set to 'MODULE'). Below these are several checkboxes for configuration options: 'Available', 'Automatic End of Day aware', 'Log Event', 'Customer Access', 'Auto Authorization', 'Head Office Function', 'Duplicate task check', 'Tanking Required', 'Dual Authorization', 'Remarks Required', 'Excel Export Required', 'Multi Branch Access', and 'Field Log Required'. The 'Tanking Required' checkbox is highlighted. Below the checkboxes is a tabbed interface with 'Main', 'Control String for functions and reports', and 'Duplicate Check Fields'. The 'Main' tab is active, showing a 'Function Description' table with columns: 'Language Code', 'Main Menu', 'Sub Menu 1', 'Sub Menu 2', 'Balloon Help', and 'Description'. The table has one row with empty input fields. At the bottom, there is a 'Field Properties' section with fields for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

To enable tanking of maintenance records for a function Id you need to select the function Id in this screen and then select the 'Tanking Required' checkbox.

For more details on this screen, refer Security Management System user manual.

Note

Tanking of records has been enabled only for the following function Ids:

- STDCIF
 - STDCUSAC
-

28.2.1 Tanking New Records

During the creation of a new record, if 'Tanking Required' option is enabled, the system tanks the details of the newly created record till the record gets authorized. Any query on this data retrieves this stored information.

28.2.2 Tanking Modified Records

All modifications to unauthorized records get tanked and the modified data gets written to actual tables only after authorization. In this case, the record remains in 'Authorized' status in the actual table and the unauthorized modifications will be kept pending for un-tanking. The most recent modifications will be shown in both summary and detailed screens with the Authorization status as 'Unauthorized'.

28.2.3 Closing a Record

You can close a record only if it is in 'Authorized' state, without any unauthorized modifications pending for un-tanking. Closure is possible only for records that are in 'Open' status. When you close a record, the system tanks this and the record gets actually closed only after the closure gets authorized.

28.2.4 Re-opening a Record

You can re-open a record only if it has been closed and the closure is authorized. Re-opening of a record gets tanked till it gets authorized and the actual re-opening happens after the authorization.

28.2.5 Authorizing a Record

All unauthorized modifications get displayed when you click 'Authorize' menu option. You can select a modification number and the records get authorized till that modification. These records are un-tanked and their status gets updated as 'Authorized'. You can authorize the modifications partially, if required.

28.2.6 Deleting a Record

All unauthorized records will be available for deletion. You can select a modification number and system deletes all unauthorized modifications from the selected modification number. If the modifications getting deleted are made by a user other than the current user, the system displays an error message.

28.2.7 Viewing Summary of Records

All summary screens display data retrieved from both the summary data source and the table that contains the unauthorized tanked records.

28.2.8 Modifying Tanking Preferences

You can modify the tanking preferences specified for a function Id, if required. This modification is possible only if all records related to that function Id are in 'Authorized' status.

29. External Deal Maintenance

29.1 Introduction

You can capture the details of a deal booked in an external system using 'External Deal' maintenance screen. You can invoke this screen by typing 'STDEXLIN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'External Deal Linkage Detail' window. It features a menu bar with 'New' and 'Enter Query' options. The main content area contains the following fields:

- FLEXCUBE Reference *
- Account Number
- External Deal Reference
- Deal Currency
- Deal Amount
- Exchange Rate
- Deal Booking Date
- Deal Expiry Date
- Account Currency
- Equivalent Amount
- Remarks

The bottom section of the window includes fields for 'Maker', 'Checker', 'Mod No', 'Date Time:', 'Record Status', and 'Authorization Status'. An 'Exit' button is positioned in the bottom right corner.

You can specify the following details in this screen:

FLEXCUBE Reference Number

This reference number is automatically generated by the system.

Account Number

Select the account number associated with the external deal from the option list which displays all valid account numbers in the system.

External Deal Reference Number

Specify a unique identification number for the external deal.

Deal Currency

Specify the currency in which the external deal was carried out or select the deal currency from the option list provided.

Account Currency

The account currency gets defaulted once you select the account number.

Deal Amount

Specify the amount associated with the external deal in terms of deal currency.

Equivalent Amount

The deal amount in terms of the account currency gets displayed here.

Equivalent Amount = Deal Amount * Exchange Rate

Exchange Rate

Specify the exchange rate to convert the deal currency in terms of the account currency.

Remarks

Specify any remarks associated with the external deal, if required.

Deal Booking Date

Specify the booking date of the external deal or select the deal booking date by clicking the 'Calendar' icon.

Deal Expiry Date

Specify the expiry date of the external deal or select the deal expiry date by clicking the 'Calendar' icon.

After specifying the above details you can save the record. An amount block equivalent to the deal amount is automatically created once these details are authorized.

Note

You can not modify a record in this screen, after it has been authorized.

For more details related to amount block maintenance, refer the chapter 'Maintaining Amount Blocks' in Current and Savings Account User Manual.

30. Annexure B - File Formats

30.1 Introduction

As mentioned earlier, SWIFT provides a country-wise holiday list that can be uploaded into Oracle FLEXCUE using the 'CCH' source code. This file consists of the 'HF' and 'HS' records. HF and HS are the tag identifiers through which the currency code can be obtained.

30.2 Upload File Formats

HF – Non-European countries

As mentioned before, the HF record comprises the holiday details for countries where 'EUR' is not the local currency. The currency code is obtained from the country code present in this record. The holiday record is then uploaded into the Oracle FLEXCUBE holiday upload table.

The HF record has the following format:

| Position | Description | Length | Type | Mandatory | Data |
|----------|-------------------|--------|-----------|-----------|-------------------------------------------------------------------|
| 1 | Tag Identifier | 2 | VAR-CHAR2 | Y | 'HF' |
| 3 | Modification Flag | 1 | VAR-CHAR2 | Y | 'A' addition 'M' modification 'D' deletion 'U' unchanged |
| 4 | Country Code | 2 | VAR-CHAR2 | Y | ISO Country Code |
| 6 | Country Name | 35 | VAR-CHAR2 | Y | Country Name (first part) |
| 41 | Country Name | 35 | VAR-CHAR2 | N | Country Name (second part) |
| 76 | Date | 8 | VAR-CHAR2 | Y | Date of a Holiday |
| 84 | Holiday type | 1 | VAR-CHAR2 | Y | Code indicating type of Holiday (see below) |

| | | | | | |
|----|------------------------|-----|-----------|---|-------------------------------------------------------------------------------------------|
| 85 | Special holi-day info. | 320 | VAR-CHAR2 | N | Restrictions applicable if a holiday is not applicable country-wide, or is not a full day |
|----|------------------------|-----|-----------|---|-------------------------------------------------------------------------------------------|

HS – For European countries

The HS record comprises the Target holiday details for countries where 'EUR' is the local currency. The holiday record is uploaded into the Oracle FLEXCUBE holiday upload table.

The HS record has the following format:

| Position | Description | Length | Type | Mandatory | Data |
|----------|-----------------------|--------|----------|-----------|-------------------------------------------------------------------------------------------|
| 1 | Tag Identifier | 2 | VARCHAR2 | Y | 'HS' |
| 3 | Modification Flag | 1 | VARCHAR2 | Y | 'A' addition 'M' modification 'D' deletion 'U' unchanged |
| 4 | Service Code | 3 | VARCHAR2 | Y | Value Added Service Code |
| 7 | Date | 8 | VARCHAR2 | Y | Date of a Holiday |
| 15 | Holiday type | 1 | VARCHAR2 | Y | Code indicating type of holiday(see below) |
| 16 | Special holi-day info | 320 | VARCHAR2 | N | Restrictions applicable if a holiday is not applicable country-wide, or is not a full day |

31. Anti-Money Laundering Reporting

31.1 Guarding Against Money Laundering

In Oracle FLEXCUBE you can guard against Money Laundering by using the anti-money laundering option wherein you will be required to maintain certain basic information as a safeguard against Money Laundering activities that customers may indulge in.

The information that you need to maintain includes the maintenance of:

- Product Categories
- Limit Codes
- Customer Groups

31.1.1 Creating Product Categories in Oracle FLEXCUBE

You have to create product categories in Oracle FLEXCUBE, for the purpose of grouping common transactions. A product is a specific service that you offer your customers. Each transaction that you process in Oracle FLEXCUBE should be linked to a product. By maintaining amount limits at the product level, each time you link a transaction with a product the system verifies the amount limit maintained for the product. If the transaction amount exceeds the amount maintained at the product level the system intimates you with an override.

You can invoke the 'AML Product Categories Maintenance' screen by typing 'CSDAMLPC' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Product Category

You should identify each product category with an identification code by giving it a unique name.

Description

With each product category you have to associate a brief description. This description is meant for information purposes and will not be used for any processing.

Limit Currency

You have to identify the currency in which limits have to be tracked for transactions associated with the product category.

A list of all the currencies maintained in Oracle FLEXCUBE is available in the option list positioned next to this field. You can select the appropriate.

Product Type

Transactions grouped under a product can either be cash based or non-cash based. Therefore, you would have created products catering to cash based and non-cash based transactions.

While creating a product category, you have to indicate whether the products grouped under the respective category cater to cash based or non-cash based transactions. You can select the appropriate option.

Exchange Rate Code and Rate Type

The rate associated with this rate code will be used to derive the exchange rate when the currency of the transaction is different from the limit currency of the product category.

Similarly, you have to select the Rate Type that is to be associated with the rate code. The options available are as follows:

- Mid
- Buy
- Sell

The rate code along with the rate type will determine the exchange rate that is to be used.

Debit/Credit Indicator

As part of Anti-Money Laundering you can indicate the manner in which the system should track the Debit and Credit turnover limits for any of the limit types, for the product category. The options available are:

- Both (Aggregate Together) – absolute values of debits and credits will be aggregated together
- Both (Aggregate Separately) – debits and credits will be aggregated separately
- Debits alone or Credits alone

Limit Code and Limit Amount

At the product category level, you can specify the limit amount that should be associated with each limit code for a limit type.

A list of all the limit codes maintained for the specific limit type (Online, Individual, Daily turnover Batch, Daily turnover Online and Monthly turnover), in the Limit Codes Maintenance screen, will be displayed in the option list positioned next to this field. You can select the appropriate limit code and specify the limit amount that is to be linked with the code.

Note

For a particular product category you can choose to maintain Limit Code and Amount combinations for all of any of the five Limit types. They are:

- The Online transaction limit
- Individual limits
- Daily turnover limits
- Monthly turnover limits
- Online daily turnover limits

The transaction limits that you specify will be tracked online on a daily basis, whenever you process a transaction involving the product category. However, individual, daily and monthly turnover limits will be tracked only when the after the End of Day processes have been run successfully.

31.2 Maintaining Limit Codes

Before you begin the maintenance of product category records, you should necessarily maintain limit codes through the Limit Code Maintenance screen. While linking a limit amount with a limit code in the product category screen, only valid limit codes that you have maintained through this screen will be made available for mapping.

You can invoke this screen by typing 'CSDAMLLM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Limit Code

You can maintain limit codes for the various types of limit types like online tracking limits, individual tracking limits, daily turnover limits and monthly turnover limits.

You have to specify a unique name to identify each Limit Code that you would like to define. Subsequently, you can assign a brief description with each limit code that you define.

Limit Type

Since you can maintain separate limit codes for each limit type, you have to associate a limit code with each limit type. The options available are:

- Online Limit – tracks the limits of all online transaction that exceed limits
- Individual Transaction – during the batch processed executed at EOD the limit maintained for this type is used to tack all individual transactions that exceed the limit
- Online Daily Turnover –all transactions processed during the day are considered for an online tracking and an online reporting is done when the specified limit exceeds
- Monthly Turnover – all transactions processed during the month that have exceeded the specified limit will be reported
- Daily Turnover – during the batch processes executed at EOD all transactions for the business day that have exceed the limit will be reported

You can select the appropriate type from the list.

31.3 Maintaining Anti Money Laundering Customer Groups

Since you need to define transaction online, individual, daily and monthly limits for each customer, each product category that you maintain should be linked with a customer. To facilitate this linking, you are required to maintain AML Customer Groups. You have to link one of the limit codes of the respective type attached to the product category to the customer group

You can define product categories applicable to customer groups through the 'AML Customer Group Maintenance' screen. You can invoke this screen by typing 'CSDAMLCG' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Customer Group

This is the AML group to which the particular customer belongs. You can select from the available option list and identify the AML group to which the customer belongs.

Note

In the CIF maintenance screen when you capture the customer code of a customer, the same will be defaulted in the AML Customer Group field since the system recognizes each customer code as a customer group. You can either choose to categorize the customer under the same group or choose another customer group.

You can capture a brief description that should be associated with every AML group

Next Review Date

While maintaining customer group and product category records you can specify the next date on which you would like to review the limits maintained for the various limit types.

Tracking

You have to specify whether the AML tracking is required for a customer or for all customers within a group. The system performs a group level tracking if you select Customer group. Conversely if you select Customer, the AML reporting, online tracking and data collection is done only at the customer level.

Note

If you fail to indicate your preference specifically the system will perform a customer group level tracking by default

Risk Profile

You can identify the risk profile of the customer group by selecting any one of the following options:

- High – indicating that the limits for the customer group need to be tracked regardless of the amount involved since the customer group is meant for high-risk customers.
- Low – indicating that the customer group is meant for low risk customers therefore amount limits need not be tracked if the amount involved falls within the limit amount.

You can select the required specification.

31.3.0.1 Linking Product Category with Customer Group

You have the option of selecting and linking as many limit codes as required for each limit type from the product categories maintained in the system. After you select the product category that is to be linked to the customer group, you have to identify the limit code associated with the limit type and in turn link it with the customer group.

Given below is a sample of the Customer Group maintenance record:

The Main details of the record are as follows:

| | |
|-----------------------|---------------------|
| Customer Group | AMLCUS01 |
| Description | AMLCUSTOMER GROUP 1 |
| Next Review Date | 10-FEB-2003 |
| Risk Profile | High |

The Product Category linkage details are as follows:

| Product Category | Description | Online Limit Code | Individual Limit Code | Daily Limit Code | Monthly Limit Code | Online Daily Turnover |
|-------------------------|--------------------|--------------------------|------------------------------|-------------------------|---------------------------|------------------------------|
| PDT01 | Product 1 | LIM31 | LIM01 | LIM11 | LIM21 | LIM41 |
| PDT02 | Product 2 | LIM36 | LIM06 | LIM16 | LIM26 | LIM46 |

Note

- Consequently, while processing transactions for all customers linked to the Customer Group AMLCUS01, the system does an online verification of transaction limits based on the amount limits maintained for the limit code LIM31 (linked to the product category PDT01) and LIM36 (linked to the product category PDT02) respectively.
 - It is mandatory for you to maintain a generic Customer Group called ALL for the customers of your bank. When product categories have not been linked to a specific customer or a customer group, the system picks up the limits maintained at the generic level for AML tracking purposes. Also, any new product category created and associated to the transaction code should be mandatorily associated with the ALL group.
-

31.4 Monitoring AML Accounting

For AML reporting purposes, while maintaining a transaction code you need to indicate whether AML monitoring is required for all accounting entries linked to the transaction code.

You can invoke this screen by typing 'STDTRNCD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

The screenshot displays the 'Transaction Code Maintenance' window. It features several sections: 'Transaction Details' with fields for Transaction Code, Description, and Swift Code; 'Availability Information' with radio buttons for Immediate, On Value Date, After Days with New Value Date, and After X days; 'Overdraft Tracking' with a dropdown for Component type for transaction; 'Preferences' with checkboxes for Cheque Mandatory, Interests and Charges Transaction Count, Interests and Charges Turnover Inclusion, Consider for Account Activity, Interest and Charges Balance Inclusion, Consider For Turnover Limit, and Consider For Cover Account; 'Anti Money Laundering Monitoring' with checkboxes for Anti Money Laundering Required, Intraday Release, Available Balance Check Required, Interests and Charges Penalty Inclusions, Inter Branch in Local Currency, Acumen Transaction Code, Exempt Advance Interest, Escrow Processing, and Available Balance Update Through PPC; and 'Fields' with labels for Maker, Checker, Mod No, Date Time, Record Status, and Authorization Status. An 'Exit' button is located in the bottom right corner.

If you indicate that AML tracking is required for transactions linked to the transaction code you have to identify the product category with which the transaction code is to be linked.

Consequently, the system does a check for every accounting entry passed during online processing. The system checks the transaction amount of the entry with the transaction online limit maintained for the specific customer group (of the customer to whose account the entry has been posted) and the product category (for the transaction code of the entry). If the system finds that the limit amount has been exceeded an override message informing you of the same will be displayed.

During the End of Day (EOD) processing, the system identifies all accounting entries posted during the day, which have been marked for AML monitoring, and verifies the individual amount limit for the customer group and product category combination and stores this data in the system. You will be able to view this data when you generate an AML report using Business Objects.

As part of the EOD processes the system also updates the daily turnover limits for the particular customer group and product category combination. Monthly turnovers are updated for the Customer Number, Product Category and Currency combination.

32. Developer and Developer Project Maintenance

32.1 Introduction

In Oracle FLEXCUBE, you can maintain details of the real-estate developer and developer projects. You can link the developers to loan accounts.

32.2 Maintaining Developer Details

You can maintain contact and project details of the developer in the 'Developer Maintenance' screen. You can invoke this screen by typing 'CSDDEVDT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

| Developer Maintenance | |
|-----------------------|----------------------|
| New Enter Query | |
| Developer Code * | Developer Name |
| Address | Telephone |
| | Email Id |
| | Fax |
| Zip | Mobile |
| Country | Website |
| Country Name | |
| Project Fields | |
| Maker | Date Time: |
| Checker | Date Time: |
| Mod No | Record Status |
| | Authorization Status |
| Exit | |

Here, you can specify the following details:

Developer Code

Specify the unique code of the developer.

Address

Specify the address of the developer.

Zip

Specify the ZIP code of the developer.

Country

Specify the code of the country to which the developer belongs. The adjoining option list displays all valid country codes maintained in the system. You can choose the appropriate one.

Country Name

The system displays the corresponding country name based on the specified code of the country.

Developer Name

Specify the name of the developer.

Telephone

Specify the telephone number of the developer.

Email ID

Specify the Email ID of the developer.

Fax

Specify the fax number that should be linked with the specified developer.

Mobile


Specify the mobile number of the developer.

Website

Specify the URL of the website linked to the developer.

32.2.1 Viewing Project Details


You can view the details of the projects linked to the developer by clicking 'Project' button in the 'Developer Maintenance' screen.



Here you can view the project names and descriptions that are linked to the specified developer.

32.2.2 Viewing UDF Details

You can view the UDF details by clicking 'Fields' button in the 'Developer Maintenance' screen.




The screenshot shows a window titled 'User Defined Fields'. Inside, there is a section labeled 'UDF Details'. At the top of this section, there are navigation controls: '<< 1 Of 1 >>' and a 'Go' button. Below this is a table with three columns: 'Field Name *', 'Value', and 'Value Description'. The table is currently empty. At the bottom right of the window, there are 'Ok' and 'Exit' buttons.

Here you can view the field names and its value.

32.3 Viewing Developer Maintenance Summary

You can view the summary of developer maintenance in the 'Developer Maintenance Summary' screen. You can invoke this screen by typing 'CSSDEVDT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



The screenshot shows a window titled 'Summary'. At the top, there are 'Advanced Search' and 'Reset' buttons. Below these are two dropdown menus: 'Authorization Status' and 'Record Status'. There is also a text field for 'Developer Code' with a search icon. Below the search fields, there is a table with columns: 'Authorization Status', 'Record Status', 'Developer Code', 'Website', 'Address', 'Developer Name', 'Country', and 'Email Id'. The table is currently empty. At the bottom right of the window, there is an 'Exit' button.

In this screen, you can query based on any combination of the following fields:

- Authorization Status
- Developer Code
- Record Status

After specifying the parameters for the query, click 'Search' button. The system displays all the records matching the parameters specified. You can view the following details:

- Authorization Status

- Record Status
- Developer Code
- Website
- Address
- Developer Name
- Country
- Email ID
- Zip

32.4 Maintaining Developer Project Details

You can maintain the details of real estate development projects in the 'Developer Project Maintenance' screen. You can invoke this screen by typing 'CSDDEVPR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Developer Project Maintenance' application window. It features a title bar, a menu bar with 'New' and 'Enter Query' options, and a main content area. The main area is divided into two sections. The top section contains form fields for 'Project Name *', 'Project Description', 'Address', and 'Status', each with a corresponding input box. To the right of these fields is a 'Developer Code *' field with an input box. The bottom section is titled 'Unit Details' and contains a table with two columns: 'Unit Id' and 'Unit Holder Name'. The table has one row with empty input boxes. Below the table is a 'Fields' section with a grid of labels: 'Maker', 'Checker', 'Mod No', 'Date Time:', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner of the window.

Here you can specify the following details:

Project Name

Specify the name of the project.

Project Description

Specify a brief description about the project.

Address

Specify the address of the project location.

Status

Specify the status of the project.

Developer Code

Specify the unique code of the developer. The adjoining option list displays all valid codes maintained in the system. You can choose the appropriate one.

Unit Details

Specify the following details.

Unit ID

Specify the unit ID of the developer project.

Unit Holder Name

Specify the name of the unit holder of the developer project.

32.4.1 Viewing UDF Details

You can view the UDF details by clicking 'Fields' button in the 'Developer Project Maintenance' screen.

| Field Name * | Value | Value Description |
|--------------|-------|-------------------|
|--------------|-------|-------------------|

Here you can specify values for the UDF.

32.5 Viewing Developer Project Maintenance Summary

You can view the summary of developer project maintenance in the 'Developer Project Maintenance Summary' screen. You can invoke this screen by typing 'CSSDEVPR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Summary

Advanced Search Reset

Authorization Status Record Status

Developer Code Project Name

Records per page 15 1 Of 1 Go

| <input type="checkbox"/> | Authorization Status | Record Status | Developer Code | Project Name | Project Description | Address | Status |
|--------------------------|----------------------|---------------|----------------|--------------|---------------------|---------|--------|
| <input type="checkbox"/> | | | | | | | |
| <input type="checkbox"/> | | | | | | | |
| <input type="checkbox"/> | | | | | | | |
| <input type="checkbox"/> | | | | | | | |
| <input type="checkbox"/> | | | | | | | |
| <input type="checkbox"/> | | | | | | | |

Exit

In this screen, you can query based on any combination of the following fields:

- Authorization Status
- Developer Code
- Record Status
- Project Name

After specifying the parameters for the query, click 'Search' button. The system displays all the records matching the parameters specified. You can view the following details:

- Authorization Status
- Record Status
- Developer Code
- Project Name
- Project Description
- Address
- Status

33. Project Financing

33.1 Introduction


Project financing is the financing of long-term infrastructure and industrial projects involving a number of equity investors and a group of banks.


Project financing is a credit facility sanctioned to the contractors who execute large infrastructure projects, residential complexes, commercial complexes, etc. These contractors are awarded the contracts (projects) based on a BID system. Once the project is awarded to a contractor, he approaches the bank seeking for finance.

The contractor can avail financing from the bank against PPC (Project Progress Certificate/ Project Payment Certificate) or Invoice or TD or a clean line. PPCs are one type of backing against which OD is provided. The contractor can be a single entity or a joint venture (JV). In case of a joint venture, the share of the overdraft for each contractor will depend on their share in the joint venture.

33.2 Processing Finance for Project

The process of project financing is as follows:





AUTO

MANUAL

1. A customer or a joint venture approaches the bank for project financing
2. The bank creates the customer in the system
3. If it is a joint venture, the bank creates the joint venture customer and enters the party/customer details linked to the joint venture in the joint venture button screen.
4. The bank then creates the project account for the created customer/joint venture customer.
5. The bank captures the following details in the 'Project Maintenance' screen:
 - Project header details
 - Sponsor/Pay-master details
 - Project milestone details

- Joint Venture Parties Details (In case of Joint Venture Limit Tracking)
 - PPC Limits Details
 - Non-PPC Limits Details
6. Link the Non-PPC lines defined in project to the project account using Limits tab
 7. The customer will utilize this clean limit line until he furnishes a PPC against part or full completion of a milestone.
 8. On receiving the PPC, the bank does the following:
 - Captures the PPC details
 - If it is a joint venture then the system will default the joint venture details to this screen based on the details captured in the project maintenance venture details screen.
 - If 'Auto Line Creation for PPC' field is unchecked,
 - You should manually create the line whenever a PPC is received.
 - The line currency can be other than project currency also, but the PPC CCY should be either project currency or line currency.
 - You should manually enter the limit line details in the project maintenance screen limits tab, if the project lines are created manually and in the PPC maintenance screen Joint Venture tab if PPC lines are created manually. If joint venture party limits tracking is not required, then the system will attach one line for the project customer with 100% tracking.
 - The system will also update the project ID and the PPC ID in the 'Facility Maintenance' screen, once the linkage between a line and a PPC/ Project is established manually during PPC maintenance
 - If 'Auto Line Creation for PPC' field is checked,
 - On authorizing the PPC, the system will create the limit lines for each of the PPC for liability ID of the project customer
 - You should allocate the limit to the project line equal to the lendable value of the respective PPC
 - You should allocate the limit to an individual customer limit lines based on the share each has in the joint venture if 'JV Limit Tracking Required' is checked
 - On authorizing the PPC, the system will automatically create line commitment contracts during the EOD. The rates used in the commitment are taken from project maintenance.
 - For each PPC authorized and if 'Limits tracking through Commitment' is checked, then the system will create the following line commitment contracts:
 - Project line commitment contract, regardless of whether there is a joint venture or not
 - Customer line commitment contract for each customer only in case of joint venture
 9. The bank will view the details of a project and the status of its collaterals from a Dashboard screen
 10. You should manually mark the PPC as CLOSED, if the payment against it has been received
 11. You should manually close the project account, if the system receives the payment towards all the PPC's and all the PPC's are marked as CLOSED
 12. When multiple lines are available and system has to utilize the lines, the priority will be determined based on the lowest interest rate + spread defined in the linkages screen.
 13. Using the PPC liquidation screen, you can choose the payment of the loan or credit to the project account. This transaction will be logged under the PPC.

14. PPC liquidation will be allowed even without the 'Entry No.', say, in case the contractor did not receive money due to contractual terms elapse etc. The system will display an override message when such an input is made.
15. Partial liquidation of PPC is allowed and they will be tracked. In case 'Entry No' is provided, loan payment will be considered only to the extent of PRINCIPAL payment and other component payments will not be considered.
16. Project closure activities include:
 - Liquidating PPCs
 - Marking PPCs as closed
 - All PPCs should be liquidated before they are closed
 - Closing all lines associated with the project
 - Manually created lines can be closed using the close button in the facility screen
 - Auto created lines (created by system) will be auto closed on the event of complete repayment and complete PPC liquidation
 - Manually closing project account
 - All lines associated with the project account should be closed
 - All PPCs should be closed
 - Manually closing project
 - All lines associated with the project should be closed
 - Commitment contracts will be auto closed on commitment maturity date through CL batch (Event: CLOC). Closure of commitment contracts before closure of project will have to be operationally controlled.

33.3 Maintaining Project Financing Transaction

Oracle FLEXCUBE allows you to maintain the project finance transaction in a bank with the details of the project undertaken with the contract. You can maintain these details using 'Project Detail and Maintenance' screen. To invoke this screen, type 'STDPJMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

33.3.1 Specifying the Project Details

Customer Number

Specify the customer number.

Project ID

Specify the project identification number.

Project Name

Specify the name of the project.

Project Account Branch

Specify the project account branch details.

Project Account

Specify the project account details.

Liability ID

Specify the liability ID.

Project Value

Specify the value of the project.

Remarks

Specify remarks, if any.

Ratio Change Allowed

Check this box if the joint venture ratio change is allowed during the course of the project.

This field is enabled only for new loans under the project financing.

JV Limit Tracking Required

Check this box if joint venture limit tracking is required.

Branch Code

The system displays the branch code.

Currency

Specify the currency details.

Number of PPCs

Specify the number of PPCs in the project.

Default PPC Clearance Days

Specify the default PPC duration for the payment.

Start Date

Specify the start date of the project.

End Date

Specify the end date of the project.

Sponsor Retention Margin (%)

Specify the retention margin for the sponsor while paying the PPC.

Bank Margin (%)

Specify the margin retained by the bank for the PPC..

Auto Line Creation for PPC

If you check this box, then the system will automatically create the credit lines while authorizing the PPC. Else, you need to manually create the line and link them in the PPC screen.

By default, this field will be checked.

Limit Track Required through Commitment

If you check this box, then the system will create the commitment contracts for every automatic line creation.

33.3.2 Specifying the Main Details

You can specify the main details of the project such as sponsor details and consultant details to validate the PPC and to recommend the sponsor for the payment.

33.3.2.1 Maintaining Sponsor Details

Sponsor ID

Specify the sponsor identification details of the project. If the sponsor is the customer of the bank, then you can specify the CIF identification details.

Sponsor Name

Specify the name of the sponsor.

The system will display the sponsor name, if you had specified the CIF ID in the 'Sponsor ID' field.

Sponsor Address

Specify the address of the sponsor.

The system will display the sponsor address, if you had specified the CIF ID in the 'Sponsor ID' field.

33.3.2.2 Maintaining Consultant Details

Consultant ID

Specify the consultant identification details of the project. If the sponsor is the customer of the bank, then you can specify the CIF identification details.

Consultant Name

Specify the name of the consultant.

The system will display the consultant name, if you had specified the CIF ID in the 'Consultant ID' field.

Consultant Address

Specify the address of the consultant.

The system will display the consultant address, if you had specified the CIF ID in the 'Consultant ID' field.

If the sponsor or consultant is not a customer of the bank, then the system will display only the name and address of the sponsor or the consultant.

33.3.3 Specifying Milestones Details

You can specify the records of the various milestones in the project and percentage of completion with respect to the project.

The screenshot displays the 'Project Details and Maintenance' window. The 'Project Details' section includes fields for Customer Number, Project ID, Project Name, Project Account Branch, Project Account, Liability No, Project Value, Remarks, Branch Code, Currency, Number Of PPCs, Default PPC Clearance Days, Start Date, End Date, Sponsor Retention Margin (%), and Bank Margin (%). There are also checkboxes for 'Ratio Change Allowed', 'JV Limit Tracking Required', 'Auto Line Creation for PPC', and 'Limit Track Required through Commitment'. Below this is a tabbed interface with 'Main', 'Milestones', 'Venture Details', 'PPC Limits', and 'Non PPC Limits'. The 'Milestones' tab is active, showing a table with columns: Milestone No, Description, Percentage Completion, Start Date, and End Date. The table has one row with empty fields. At the bottom, there is a 'UDF' section with fields for Maker, Checker, Mod No, Date Time, Record Status, and Authorization Status, along with an 'Exit' button.

| Milestone No * | Description * | Percentage Completion * | Start Date * | End Date * |
|----------------|---------------|-------------------------|--------------|------------|
| | | | | |

Milestone No

Specify the milestone number.

Description

Specify the description of the milestone.

Percentage Completion

Specify the percentage of completion with respect to the milestone.

Start Date

Specify the start date of the milestone.

End Date

Specify the end date of the milestone.

33.3.4 Specifying the Venture Details

You can maintain the details of the joint venture. You can also change the joint venture ratios during the course of the project, but these ratios are effective only for future loans. Each loan created for the project can store the ratios at the loan level which is defaulted based on the application ratio at the time of loan creation. All limits tracking for joint venture parties will be based on this ratio.

The system will create the limit lines for each of the project venture parties when joint venture limit tracking is required at the project level. The line ID maintained at the limits is used to create the limits automatically. Each time the PPC is created, the system will create a new limit line using the same line for each of the liability of each joint venture. Different joint venture parties will have the same commitment product which can have different interest rate.

The screen is as shown below:

Project Details and Maintenance

New Enter Query

Project Details

Customer Number *
Project ID *
Project Name *
Project Account Branch *
Project Account *
Liability No *
Project Value *
Remarks

Branch Code
Currency *
Number Of PPCs *
Default PPC Clearance Days *
Start Date *
End Date *
Sponsor Retention Margin (%)
Bank Margin (%)

☒ Ratio Change Allowed
☒ JV Limit Tracking Required
☒ Auto Line Creation for PPC
☒ Limit Track Required through Commitment

Main Milestones **Venture Details** PPC Limits Non PPC Limits

Default

1 Of 1 Go

Effective Date *

Party ID * Party Name Liability No * Ratio * Rate * Margir

UDF

Maker Date Time:
Checker Date Time:
Mod No Record Status
Authorization Status

Exit

Effective Date

Specify the effective date of the joint venture. For each effective date, the system maintains the ratio among the joint venture partners. The sum of ratios for each effective date must be equal to 100.

Party ID

The system displays the joint venture details of the project.

Party Name

The system will display the party name.

Liability ID

Specify the liability ID.

Ratio

Specify the percentage share of the joint venture party. The sum of all the ratios must be equal to 100.

Default Interest Rate

Specify the default interest rate that is used for the external component in the commitment product. The system will default this value to PPC.

Margin

Specify the margin applicable on the interest rate.

33.3.5 Specifying PPC Limits Details

You can create the clean limit (ToD) manually using the line ID for the amount. You should then link this limit to the project account. The system creates the joint venture lines on authorization of the PPC maintenance with joint venture tracking required.

In case of manual line creation, the system will create the lines in project currency. Whenever there is a cross currency, the system will use a standard mid rate to convert from limit currency to project currency to track utilization. The LCY difference that may arise due to exchange rate differences will be handled by the ELCM CCY revaluation EOD batch.

You can view the limits detail such as line ID to create the project limits. There are two types, namely, PPC Limits and Non PPC Limits.

The screenshot for PPC Limits is as follows:

The screenshot displays the 'Project Details and Maintenance' window. The 'Project Details' section includes fields for Customer Number, Project ID, Project Name, Project Account Branch, Project Account, Liability No, Project Value, and Remarks. It also has checkboxes for 'Ratio Change Allowed', 'JV Limit Tracking Required', 'Auto Line Creation for PPC', and 'Limit Track Required through Commitment'. The 'PPC Limits' tab is selected, showing a table with columns: Limit Type, Limit Description, Credit Line, Serial No, and Commitment Product. The table contains one row with Serial No '1'. The bottom section includes fields for Maker, Checker, Mod No, Date Time, Record Status, and Authorization Status, along with an 'Exit' button.

| Limit Type * | Limit Description | Credit Line * | Serial No * | Commitment Product |
|--------------|-------------------|---------------|-------------|--------------------|
| | | | 1 | |

Limit Type

Specify the type of limit.

Limit Description

The system displays the limit description.

Credit Line

Specify the credit line.

Serial No

The system displays the serial number for the limit created.

Commitment Product

Specify the commitment product details used when the respective limit line is created.

Rate

Specify the rate.

Margin

Specify the margin.

33.3.6 Specifying Non PPC Limits Details

The screenshot for Non PPC Limits is as follows:

The screenshot displays the 'Project Details and Maintenance' window. The 'Project Details' section includes fields for Customer Number, Project ID, Project Name, Project Account Branch, Project Account, Liability No, Project Value, Remarks, Branch Code, Currency, Number Of PPCs, Default PPC Clearance Days, Start Date, End Date, Sponsor Retention Margin (%), and Bank Margin (%). There are also checkboxes for 'Ratio Change Allowed', 'JV Limit Tracking Required', 'Auto Line Creation for PPC', and 'Limit Track Required through Commitment'. The 'Non PPC Limits' tab is selected, showing 'Joint Venture Line Details' and 'Party Line Details' sections. The 'Joint Venture Line Details' section has a table with columns: Limit Type, Limit Description, Customer No, Liability No, and Line Code. The 'Party Line Details' section has a table with columns: Customer No, Liability No, Line Code, Line Serial, and Currency. The bottom of the window shows a 'UDF' section with fields for Maker, Checker, Mod No, Date Time, Record Status, and Authorization Status, along with an 'Exit' button.

33.3.6.1 Maintaining Joint Venture Line Details

Limit Type

Specify the type of limit.

Limit Description

The system displays the limit description.

Customer No

Specify the customer number.

Liability No

Specify the liability number.

Line Code

Specify the line code.

Line Serial

The system displays the serial number for the limit created.

Currency

The system displays the line currency details.

Rate

Specify the rate.

Margin

Specify the margin.

JV Line

This box will be checked by default.

33.3.6.2 Maintaining Party Line Details**Customer No**

Specify the customer number.

Liability No

Specify the liability number.

Line Code

Specify the line code.

Line Serial

The system displays the serial number for the limit created.

Currency

The system displays the line currency details.

33.4 Maintaining PPC

Oracle FLEXCUBE allows the executor to maintain the PPC during the course of the project, i.e. during the course of the project, once the executor completes the milestone should inform the sponsor. The sponsor in turn, will inspect and confirms the completion of the milestone. The executor is then allowed to raise the PPC with start date and the expiry date. The system calculates the expiry date based on the default PPC clearance days. However, the sponsor can change the expiry date. The system will accept the PPC in any currency. If there is a cross currency, then the system uses a standard mid rate for converting from limit currency to project currency.

You can maintain the PPC using 'PPC Maintenance' screen. To invoke this screen, type 'STDPPCMN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

33.4.1 Specifying PPC Maintenance Details

Project ID

Specify the project ID.

PPC ID

The system displays the PPC ID.

PPC Description

Specify the description of the PPC.

Start Date

Specify the PPC start date.

End Date

Specify the PPC end date.

Milestone No

Specify the milestone sequence number.

Currency

Specify the currency of the PPC.

PPC Amount

Specify the amount of the PPC. If the sum of the PPC amounts for all the PPCs presented for the specific milestone is greater than the milestone percentage calculated amount an error message is displayed.

The system will create the automatic limit lines for the lendable amount arrived at after applying the sponsor retention margin and the bank margin.

Sponsor Retention Margin

The system displays the margin retained by the sponsor for this PPC. However, you can amend this field while creating the PPC.

Sponsor Amount

The system displays the sponsor amount after applying the sponsor retention margin.

Bank Margin

The system displays the margin retained by the bank for this PPC. However, you can amend this field while creating the PPC.

Lendable amount

The system displays the lendable amount after applying the bank margin.

Amount Paid

The system displays the amount that has been paid against this PPC.

Remarks

Specify remarks, if any.

33.4.2 Specifying Joint Venture Details

In case of manual line linkage, you need to operationally ensure the following points:

- Synchronization of Line End date and PPC end date
- Limit lines should have amounts equivalent to that of PPC lendable amount. In case line currency is different from PPC currency, lines should be created for the equivalent of PPC lendable amount by applying the rate conversion. If there is any mismatch in the amounts, while linking the manual lines, the system will display an override message

Party ID

The system defaults the party ID from the project maintenance.

Ratio

The system defaults the joint venture share ratio from the project maintenance.

Credit Line

The system defaults the line ID. The system uses this limit line for tracking the exposure of specific joint venture party.

If joint venture limit tracking is not required at project level, the system will not create the lines. In case auto creation of lines is not chosen, then you need to manually create limit lines and link them in this screen.

Serial Number

Specify the line serial of the credit line.

Currency

The system displays the line currency.

After specifying the PPC amount, click on 'CALC' button. The will calculate the sponsor margin and the bank margin and arrive at the sponsor amount and the lendable amount respectively.

33.4.3 Maintaining PPC Liquidation

You can maintain the liquidation details in the PPC screen, where in you can choose the payment of the loan or credit to the project account. This transaction is logged in the PPC. To invoke the PPC Liquidation screen, type 'STDPPCLQ' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

PPC Liquidation

New Enter Query

PPC Liquidation

| | | | |
|-----------------|--|-----------------------|--|
| Project ID * | | Branch Code * | |
| Project Name | | Loan/Account Number * | |
| PPC Id * | | Entry Number | |
| PPC Description | | Currency | |
| Serial No | | Amount | |

UDF

Maker Date Time:

Checker Date Time:

Mod No Record Status

Authorization Status

Exit

Project ID

Specify the project ID.

Project Name

The system displays the name of the project ID selected.

PPC ID

Specify the PPC ID.

PPC Description

The system displays the description for the PPC ID selected.

Loan/Account Number

Specify the loan or the account number.

Entry Number

Specify the entry number. If you have not specified the entry number, then the system will display an override message.

Amount

The system displays the amount for liquidation. However, you can amend this field.

Branch Code

Specify the branch code.

Currency

The system displays the currency details.

33.5 Viewing Dashboard Details

Oracle FLEXCUBE allows you to view the details of the PPC available in the project such as joint venture ratios, balance in the project account, the project lines and their limits for each project line, etc. You can view these details using 'Dashboard Details' screen. To invoke this screen, type 'STDPJDSH' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Dashboard Detail

New Enter Query

Project ID Customer ID Account No
Project Name Customer Name Account CCY
Project Amount Available Balance Current Balance
Project Utilization Currency

PPC Details Limit Details Commitment Details Loan Details

1 Of 1

| Collateral Type | Sequence | Collateral Description | Amount | Currency | Out Standing | Status |
|-----------------|----------|------------------------|--------|----------|--------------|--------|
| | | | | | | Open |

1 Of 1

| Party ID | % Share | Currency | Limit | Available |
|----------|---------|----------|-------|-----------|
| | | | | |

Exit

You can view the following details:

- Project ID
- Project Name
- Customer ID
- Customer Name
- Available Balance
- Account Number
- Account Currency
- Project Limit
- Project Utilization
- Current Balance

33.5.1 Viewing PPC Details

You can view the PPC details by clicking on the 'PPC Details' tab in the 'Dashboard Details' screen.

The screen is as shown below:

Dashboard Detail

New Enter Query

Project ID Customer ID Account No
Project Name Customer Name Account CCY
Project Amount Available Balance Current Balance
Project Utilization Currency

PPC Details Limit Details Commitment Details Loan Details

| Collateral Type | Sequence | Collateral Description | Amount | Currency | Out Standing | Status |
|----------------------|----------------------|------------------------|----------------------|----------------------|----------------------|--------|
| <input type="text"/> | <input type="text"/> | <input type="text"/> | <input type="text"/> | <input type="text"/> | <input type="text"/> | Open |

| Party ID | % Share | Currency | Limit | Available |
|----------------------|----------------------|----------------------|----------------------|----------------------|
| <input type="text"/> | <input type="text"/> | <input type="text"/> | <input type="text"/> | <input type="text"/> |

Exit

You can view the following details:

- Collateral Details
 - Collateral Type
 - Sequence
 - Collateral Description
 - Amount
 - Outstanding
 - Status
- Venture Details
 - Party ID
 - % Share
 - Limit CCY
 - Limit
 - Available

33.5.2 Viewing Limit Details

You can view the limit details by clicking on the 'Limit Details' tab in the 'Dashboard Details' screen.

The screen is as shown below:

Dashboard Detail

New Enter Query

Project ID Customer ID Account No
Project Name Customer Name Account CCY
Project Amount Available Balance Current Balance
Project Utilization Currency

PPC Details **Limit Details** Commitment Details Loan Details

| Credit Line | Line Serial | Currency | Limit | Utilized | Paid |
|-------------|-------------|----------|-------|----------|------|
|-------------|-------------|----------|-------|----------|------|

| Party ID | % Share | Credit Line | Line Serial | Currency | Limit | Utilized |
|----------|---------|-------------|-------------|----------|-------|----------|
|----------|---------|-------------|-------------|----------|-------|----------|

Exit

You can view the following details:

- Project Line Details
 - Line ID
 - Line Serial
 - Limit
 - Utilized
 - Paid
- Customer Line Details
 - Party ID
 - % Share
 - Line ID
 - Line Serial
 - Limit
 - Utilized
 - Paid

33.5.3 Viewing Commitment Details

You can view the commitment details by clicking on the 'Commitment Details' tab in the 'Dashboard Details' screen.

The screen is as shown below:

The screenshot shows a web application window titled "Dashboard Detail". At the top, there are buttons for "New" and "Enter Query". Below these are input fields for Project ID, Project Name, Project Amount, Project Utilization, Customer ID, Customer Name, Available Balance, and Currency. To the right, there are input fields for Account No, Account CCY, and Current Balance. A tabbed interface is present with four tabs: "PPC Details", "Limit Details", "Commitment Details" (which is selected and highlighted in blue), and "Loan Details". Below the tabs is a table with a header row containing "Contract Reference", "Currency", "Amount", "Outstanding Amount", and "Maturity Date". The table body is currently empty. At the bottom right of the window is an "Exit" button.

You can view the following details:

- Contract Reference
- Currency
- Amount
- Outstanding Amount
- Maturity Date

33.5.4 Viewing Loan Details

You can view the loan details by clicking on the 'Loan Details' tab in the 'Dashboard Details' screen.

The screen is as shown below:

This screenshot is identical to the one above, showing the "Dashboard Detail" window. However, the "Loan Details" tab is now selected and highlighted in blue, while "Commitment Details" is no longer the active tab. The table below the tabs remains empty, and all other UI elements are the same.

You can view the following details:

- Contract Reference
- Currency
- Amount
- Outstanding Amount
- Maturity Date

33.6 Querying Dashboard Details

Oracle FLEXCUBE allows you to query the dashboard details based on the Project ID, Project Name, Customer ID, Customer Name, Account Number. You can view these details using 'Dashboard Summary' screen. To invoke this screen, type 'STSPJDSH' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Dashboard Summary

Advanced Search Reset

Project ID Project Name

Customer ID Customer Name

Account No Account CCY

Project Amount

Records per page 15 1 Of 1 Go

| <input type="checkbox"/> | Project ID | Project Name | Customer ID | Customer Name | Account No | Account CCY | Project Amount |
|--------------------------|------------|--------------|-------------|---------------|------------|-------------|----------------|
| <input type="checkbox"/> | | | | | | | |
| <input type="checkbox"/> | | | | | | | |
| <input type="checkbox"/> | | | | | | | |
| <input type="checkbox"/> | | | | | | | |
| <input type="checkbox"/> | | | | | | | |
| <input type="checkbox"/> | | | | | | | |

Exit

You can query the record based on the following details:

- Project ID
- Customer ID
- Account Number
- Project Limit
- Project Name
- Customer Name
- Account Currency

You can double-click on a specific record to view the detailed screen.

33.7 Querying Accounting Entries

Oracle FLEXCUBE allows you to view the accounting entry serial number which can be used in PPC liquidation screen for marking a specific credit entry for query. You can view these details using 'rCustomer Account Transaction Query' screen. To invoke this screen type 'ACDTRNQY' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button

The screen is as shown below:

Customer Account Transaction Query

Execute Query

Query Criteria

Contract Reference

Account Number

Transaction Code

Event Code

Value Date

Related Reference Number

From Date

Last N number of transactions

Debit/Credit

Transaction Currency

Module

Transaction Date

Related Account

To Date

Account Details

Branch

Currency

Starting Balance

Debit Credit Balance

Account Number

Transaction Details

1 Of 1 Go

| Contract Reference | Entry Serial Number | Module Code | Transaction Code | Event Code | Transaction Date | Value |
|--------------------|---------------------|-------------|------------------|------------|------------------|-------|
|--------------------|---------------------|-------------|------------------|------------|------------------|-------|

Cancel

You can query the record based on the following details:

- Contract Reference
- Account Number
- Debit/Credit
- Transaction Code
- Currency
- Event Code
- Module Code
- Value Date
- Transaction Date
- Related Reference
- Related Account
- From Date
- Last N Number of Transactions
- To Date
-
-
-
-

Clicking on the 'Query' button, the system displays the transaction details. You can double-click on a specific record to view the detailed screen.

Note

- You can query for a specific number of previous records by entering the value in 'Last N Number of Transactions'. By default, it is set as 100.
 - When you click 'Query' button, the system validates whether Last N.number of transactions is greater than the menu level MAX_RES_ROWS of the function ID 'ACDTRNQY'. If it is found greater than that, then the system displays a configurable message 'Last N number of transactions is greater than the allowed maximum transactions to be retrieved'.
 - If you do not enter the last N number of transaction and click the 'Query' button, and the number of transactions to be retrieved is greater than the menu level MAX_RES_ROWS for the function ID 'ACDTRNQY', then the system will retrieve only the first MAX_RES_ROWS number of transaction and display an information message 'Displaying only first[MAX_RES_ROWS] transactions'.
 - The starting balance and running balance fields of the Customer Account Transaction Query (ACDTRNQY) are not be applicable if you try to retrieve the Last N transaction.
-

34. Error and Error Codes for Project Financing

34.1 Error and Error Codes

| Validation | Error Code | Description |
|-----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|-------------|--------------------------------------------------------------------------------------------------------|
| System should not allow entering PPCs if the total # of PPC's already entered exceeds the # allowed | ST-PPC-001 | Max limit for number of PPCs exhausted. |
| Whenever there is a change in the # of PPC's, the system should validate whether the change is an increase or decrease. It should only allow an increase in the # of PPC's | ST-CON003 | Decreasing number of PPCs not allowed |
| At the project maintenance, whenever there is a change in the project amount, the system should validate and only allow an increase in the project amount and not allow a decrease | ST-CON005 | Decrease of project amount not allowed |
| In case of a JV, the total of the % share of individual customers should be 100% | ST-PROJ-009 | Total share should be 100% |
| In case of a JV, each customer should have a separate Liability ID it is operational control. At the project maintenance, each project should have unique Line ID for PPC lines. | ST-PROJ-028 | Liability ID already in use |
| The milestone start date and end date should be validated against that of the project | ST-PROJ-004 | The milestone start date/end date should be equal to or within the range of project start and end date |
| The project status when changed to CLOSED should be allowed only when all PPC's associated with the respective project are in CLOSED status | ST-PROJ-024 | OPEN PPC's exist. Project status cannot be closed |
| In case of auto created lines, system should not allow amendment on these lines | ST-CON012 | Amendment of auto-created lines not allowed |
| The number of milestones cannot exceed the number of PPCs | ST-PROJ-027 | Number of milestones cannot be greater than the number of PPCs |

| | | |
|-------------------------------------------------------------------------------------------|-------------|-------------------------------------------------------------------------|
| The sum of the milestone percentage completion should be 100 | ST-PROJ-010 | The sum of milestone completion should be 100 |
| PPC end date is different from PPC start date + PPC clearance days. Configurable override | ST-PROJ-031 | PPC End Date is different from Project Start Date + PPC Clearance days. |

35.1 Introduction

You can generate the following reports:

- List of deleted transactions
- Accounting journal
- Cash flow report
- Balances of future dated transactions
- Current Rates Report
- Account Opening Confirmation
- Activity Journal Report
- Core Exception Report

35.2 List of Deleted Transactions

This report lists out the deleted transaction details pertaining to each product under each module pertaining to every user. You can invoke this screen by typing 'ACRDLTXN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Specify the following details.

Module

Indicate whether the reports should be generated for a single module or for all modules.

If you choose 'Single', you need to specify the module for which the report needs to be generated. The option list provided displays all valid module codes maintained in the system. You can select the appropriate one.

Transactions

Indicate the type of transactions that should be covered in the report. The following options are available:

- All
- This branch
- Posted to Other Branch

- This branch acted as bridge

Products

Indicate whether the reports should be generated for a single product or for all products.

If you choose 'Single', you need to specify the product code for which the report needs to be generated. The option list provided displays all valid product codes maintained in the system. You can select the appropriate one.

User

Indicate whether the reports should be generated for a transactions entered by all users or a single user.

If you choose 'Single', you need to specify the user ID based on which the report needs to be generated. The option list provided displays all valid user IDs maintained in the system. You can select the appropriate one.

From

Specify the batch from which the transactions need to be considered for report generation.

To

Specify the batch until which transactions need to be considered for report generation.

Print Copies

Check this box to indicate that the report needs to be printed.

Click 'OK' to generate the report.

35.2.1 Contents of Report

The contents of this report are discussed under the following heads:

Header

The Header carries the title of the report, information on the branch code, branch date, the ID of the user who generated the report, the date and time at which it was generated, the modules covered in the report, the product codes covered in the report, batch information, transactions covered in the report and printing preference.

Body of the Report

This report is sorted module-wise. For every module the following details are displayed.

- Module
- Product
- User ID

The following transaction details are displayed.

| Field Name | Field Description |
|------------------|---------------------------------------------------------|
| Reference Number | This is the reference number of the deleted transaction |
| Account Branch | This is the branch where the account resides. |
| Account Number | This is the account number. |

| | |
|-------------------------|----------------------------------------------------------------------------------------------------|
| Currency | This is the currency of the transaction. |
| Debit/Credit | This indicates the nature of the transaction – debit or credit. |
| Transaction Code | This is the transaction code. |
| Status | This is the status of the transaction |
| Value Date | Indicates the value date of the transaction |
| Account description | This is the account description. |
| Fcy Amount | This is the transaction amount in foreign currency. |
| Transaction Description | This is the description of the transaction code |
| Exchange Rate | This is the exchange rate |
| LCY Amount | This is the Amount in Local currency |
| Narrative | This is the narrative text associated with the transaction. |
| Instrument Number | This is the instrument number linked to the transaction. |
| Auth ID | This is the authorization ID |
| Total Debits | Total amount debited under the respective user, product and module |
| Total Credits | Total amount credited under the respective user, product and module |
| User ID | This is the user ID of the user who entered the transaction. |
| Grand Total Debits | This is the grand total amount of all the debit transaction grouped by transaction code and user. |
| Grand Total Credits | This is the grand total amount of all the credit transaction grouped by transaction code and user. |

35.3 Accounting Journal

This report gives details of every journal entry transaction. You can invoke this screen by typing 'ACRJRNAL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Accounting Journal' window with the following sections:

- Module:** Radio buttons for 'Single' and 'All'. A text field with a selection icon is below.
- Products:** Radio buttons for 'Single' and 'All'. A text field with a selection icon is below.
- User:** Radio buttons for 'Single' and 'All'. A text field with a selection icon is below.
- Batch:** 'From' and 'To' text fields with selection icons.
- Transactions:** Radio buttons for 'All', 'This Branch', 'Posted to Other Branch', and 'This Branch acted as Bridge'. Checkboxes for 'Print Copies' and 'Position Entries' are also present.
- Report Date:** A text field with a selection icon.
- Report Format:** A dropdown menu currently set to 'PDF'.
- Report Output:** A dropdown menu currently set to 'Print'.
- Printer At:** A dropdown menu currently set to 'Client'.
- Printer:** A text field with a selection icon.
- Buttons:** 'Ok' and 'Exit' buttons at the bottom right.

Specify the following details:

Module

Indicate whether the reports should be generated for a single module or for all modules.

If you choose 'Single', you need to specify the module for which the report needs to be generated. The option list provided displays all valid module codes maintained in the system. You can select the appropriate one.

Transactions

Indicate the type of transactions that should be covered in the report. The following options are available:

- All
- This branch
- Posted to Other Branch
- This branch acted as bridge

Products

Indicate whether the reports should be generated for a single product or for all products.

If you choose 'Single', you need to specify the product code for which the report needs to be generated. The option list provided displays all valid product codes maintained in the system. You can select the appropriate one.

User

Indicate whether the reports should be generated for a transactions entered by all users or a single user.

If you choose 'Single', you need to specify the user ID based on which the report needs to be generated. The option list provided displays all valid user IDs maintained in the system. You can select the appropriate one.

From

Specify the batch from which the transactions need to be considered for report generation.

To

Specify the batch until which transactions need to be considered for report generation.

Print Copies

Check this box to indicate that the report needs to be printed.

Position Entries

Check this box to indicate that the report needs to cover position accounting entries.

Report Date

Specify the date as on which the report needs to be generated.

Click 'OK' to generate the report.

35.3.1 Contents of Report

The contents of this report are discussed under the following heads:

Header

The Header carries the title of the report, information on the branch code, branch date, the ID of the user who generated the report, the date and time at which it was generated, the modules covered in the report, the product codes covered in the report, batch information, transactions covered in the report and printing preference.

Body of the report

The report is sorted by modules. Under every module, it lists out product-wise transaction details.

The following transaction details are displayed.

| Field Name | Field Description |
|------------------|-----------------------------------------------------------------|
| Product | This is the product code of the transaction. |
| User Id | This is the user ID of the user who entered the transaction. |
| Reference No | This is the transaction reference number. |
| Account Branch | This is the account branch. |
| Account Number | This is the account number. |
| Currency | This is the currency of the transaction. |
| Dr/Cr | This is the nature of the transaction – either debit or credit. |
| Transaction Code | This is the transaction code while posting the journal entry. |
| Module | This is the module code of the report |
| Description | This is the description of the transaction code. |
| Status | Status of the transaction. |

| | |
|---------------------|----------------------------------------------------------------------------------------------------|
| Value Date | This is the value date of the transaction. |
| Account Description | This is the description of the account. |
| Event | This is the event triggered on the transaction. |
| Fcy Amount | This is the transaction amount in a foreign currency |
| Exchange Rate | This is the exchange rate used if the transaction is in any other currency. |
| Lcy Amount | This is the transaction amount in local currency. |
| Auth ID | This is the user ID of the user who authorized the transaction. |
| Total Debits | Total amount debited under the respective user, product and module |
| Total Credits | Total amount credited under the respective user, product and module |
| Grand Total Debits | This is the grand total amount of all the debit transaction grouped by transaction code and user. |
| Grand Total Credits | This is the grand total amount of all the credit transaction grouped by transaction code and user. |

35.4 Cash Flow Report

The 'Cash flow report' gives details of the cash flow by accounts or by account class. The report contains details of the Account Number or Account Class, and the list of Accounts or Account Classes. You can invoke this screen by typing 'ACRPCASH' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

Specify the following details.

Report Name

Specify the name of the report. The option list provided displays all valid reports maintained in the system. You can select the appropriate one.

Report Type

Indicate whether the report should be a detailed report or a summary report.

Notice Contracts

Check this box to indicate that notice contracts should be covered in the report.

Call Contracts

Check this box to indicate that call contracts should be covered in the report.

Select Account Class/Account

Indicate whether the reports should be generated based on account class or account.

All/Specific Records

Indicate whether the reports should be generated for all records in an account class/account or for specific records.

Account Class

If you have indicated 'Account Class' as the basis for report generation, specify the account classes that should be considered. Click add icon to add rows. You can select a valid account class from the adjoining option list.

Account

If you have indicated 'Account' as the basis for report generation, specify the accounts that should be considered. Click add icon to add rows. You can select a valid account from the adjoining option list.

Click 'OK' to generate the report.

Note

Cash flow report does not display all the transactions for an account. It displays the transactions only with amount due.

35.4.1 Contents of Report

The contents of the cash flow report are discussed under the following heads:

Header

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report, the module, page number and the date and time at which it was generated.

Body of the Report

The report is sorted on the currency of the cash flow.

| Field Name | Field Description |
|------------|-------------------|
|------------|-------------------|

| | |
|---------------|-----------------------------------------------------------------------------------|
| Interval | Indicates the interval of cash flow |
| Amount In | This is the amount debited into the particular account for the particular period. |
| Account | This is the account number |
| Account Class | This indicates the account class |
| Amount Out | This is the amount credited from the account during the specified period. |
| Net Flow | Indicates the net flow |
| Currency | Indicates the currency of the transaction |

35.4.2 **Cash Flow (Summary) Report**

The Cash Flow summary report summarizes the details of cash flow for particular Accounts or Account Classes.

Header

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report and the date and time at which it was generated.

Body of the Report

The report is sorted on the currency of the cash flow for different account classes and their accounts. The following details are displayed.

| Field Name | Field Description |
|-------------------|--------------------------------------------------------------------------------|
| Amount In | This is the amount debited into the particular account for the specific period |
| Amount Out | This is the amount credited from the account during the specified period |
| Net Flow | This is the net amount available in the account for the specified period |

35.5 Future Dated Account Balance Report

This report gives balances of future dated transactions. You can invoke the screen by typing 'ACRPFVBL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Future Dated Contracts' window. It contains sections for selecting account criteria and report preferences. The 'Account Class' section is active, showing a list of account classes. The 'Report Preferences' section shows 'All Records' selected. The bottom of the window has options for report format (PDF), output (Print), printer location (Client), and printer name. 'Ok' and 'Exit' buttons are at the bottom right.

You can specify the following parameters:

Select Account Class/Account

Select account criteria for generating the report from the following options:

- Account Class
- Account

Report Preferences

Select report preference criteria for generating the report from the following options:

- All Records
- Specific Records

Account Class

Specify valid account classes for which you need to generate the report from the adjoining option list, if you have selected 'Account Class'.

Account

Specify valid account classes for which you need to generate the report from the adjoining option list, if you have selected 'Account'.

35.5.1 Contents of the Report

Header

The Header carries the title of the report, information on the branch code, branch date, the ID of the user who generated the report, the date and time at which it was generated and the modules covered in the report.

Body of the Report

The following details are displayed.

| Field Name | Field Description |
|------------------|-------------------------------------------------------------------------------------|
| Date | This gives the date for which a future dated transaction is booked for the account. |
| Reference Number | This is the reference number of the future dated transaction |
| Inflow | This is the inflow amount. |
| Outflow | This is the outflow amount. |
| Balance | This is the available balance. |
| Currency | This is the currency of the account |
| Customer | This is the name of the customer. |
| Account | This is the account number of the customer. |
| Account Class | This is the account class. |
| Opening | This is the opening balance of the account. |

35.6 Current Rates Report

This report gives details on rates for currency pairs. You can invoke the screen by typing 'CYRTCURR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Currency Rates

Selection

☒ All Currency Pairs
☐ Selected Currency Pair

Currency Choice

Currency1 Currency2

Report Format Printer At

Report Output Printer

Ok Exit

Specify the following details.

Selection

Indicate whether the report should be generated for all currency pairs or for a given currency pair.

Currency 1

If you have chosen, 'Selected Currency Pair', then specify the first currency that forms a pair. The adjoining option list displays all valid currency codes maintained in the system. You can select the appropriate one.

Currency 2

If you have chosen, 'Selected Currency Pair', then specify the second currency that forms the pair. The adjoining option list displays all valid currency codes maintained in the system. You can select the appropriate one.

Click 'OK' to generate the report.

35.6.1 Contents of Report

Header

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report, the date and time at which it was generated, the module covered in the report and reporting options.

Body of the report

The report is sorted by currency pairs. The following details are displayed.

| Field Name | Field Description |
|-------------------|------------------------------------------------------------------------------------|
| Currency Pair | This gives the currency pairs for which rate report has been generated. |
| Quotation | This indicates the quotation type – either direct or indirect. |
| No. of Units | This indicates the number of units of one currency being quoted against the other. |
| Rate Type | This is the rate type. |
| Mid Rate | This is the mid rate used for conversion. |
| Buy Rate | This is the buy rate used for conversion. |
| Sale Rate | This is the sell rate used for conversion. |

35.7 Rate History Report

This report gives details on history of rates for currency pairs. You can invoke the screen by typing 'CYRTHIST' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Report For

☒ All Currency Pairs
☐ Selected Currency Pair

Selected Pair

Currency 1 Currency 2

Date Range

From Date To Date

Report Format
 Report Output

Printer At
 Printer

Ok Exit

Specify the following details.

Report For

All Currency Pairs

Select if you need all currency pairs.

Selected Currency Pair

Select if you need selected currency pair.

Selected Pair

Currency 1

If you have chosen, 'Selected Currency Pair', then specify the first currency that forms a pair. The adjoining option list displays all valid currency codes maintained in the system. You can select the appropriate one.

Currency 2

If you have chosen, 'Selected Currency Pair', then specify the second currency that forms the pair. The adjoining option list displays all valid currency codes maintained in the system. You can select the appropriate one.

Date Range

From Date

Specify the from date.

To Date

Specify the to date.

Click 'OK' to generate the report.

Header

The Header carries the title of the report, information on the branch code, branch date, the ID of the user who generated the report, the date and time at which it was generated, the module covered in the report, reporting options, currency pair, from date and to date .

Body of the report

The report is sorted by currency pairs. The following details are displayed.

| Field Name | Field Description |
|---------------|------------------------------------------------------------------------------------|
| Currency Pair | This gives the currency pairs for which rate report has been generated. |
| Quotation | This indicates the quotation type – either direct or indirect. |
| No of Units | This indicates the number of units of one currency being quoted against the other. |
| Rate Type | This is the rate type. |
| Date | The effective date of the rates applied. |
| Mid Rate | This is the mid rate used for conversion. |
| Buy Rate | This is the buy rate used for conversion. |
| Sale Rate | This is the sell rate used for conversion. |

35.8 Customer Account Opening Confirmation Report

You can generate a report for the customer, confirming that his / her account with the bank has been successfully opened. This report contains the following details:

- Customer Type
- Customer Number
- Date

You can generate the Customer Account Opening Confirmation report for one customer or all the customers at once, as of a specific date. To generate the report, invoke 'Customer Account Opening Confirmation' screen.

You can invoke this screen by typing the code 'CSRPACKO' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

The screen is as shown below:

Customer Account Opening Confirmation

Customer Type ☒ All Customers
☐ Single

Customer Number

Date

Report Format

Report Output

Printer At

Printer

Ok Exit

Customer Type

You can generate customer account opening confirmation report for one or all the customers. Indicate your choice here. If you select 'Single Customer', you have to specify the customer number in the space provided.

Customer Number

If you wish to generate a report specific to one customer, specify the customer number. The option list displays all valid customer numbers maintained in the system. Select the appropriate one.

Date

Specify the date as of which you want to generate the report.

Once you have set the preferences, click 'OK' button. The system displays the print option screen, where you can set your preferences as to viewing and printing the report.

35.8.1 Contents of the Report

The contents of the report are discussed under the following heads:

Header

The Header carries the title of the report, information on the branch code, the run date and time, the branch date, the user id, the module name and the page number of the report.

Body of the Report

| Field Name | Field Description |
|------------------------------|--------------------------------------------------------------------------------|
| Customer Name | Indicates the name of the customer |
| Customer Number | Indicates the customer number |
| First Nominee | Indicates the name of the first nominee |
| Second Nominee | Indicates the name of the second nominee |
| Address | Indicates the contact address for the customer whose cheque has been rejected. |
| Client Account Number | Indicates the Account Number of the client |
| Subject | Indicates the subject |
| Account Details | |
| First Account Holder Details | |
| Name | Indicates the name |
| Address | Indicates the address |
| Street | Indicates the street |
| Place | Indicates the place |
| Date of Birth | Indicates the date of birth |
| Telephone | Indicates the telephone |
| Fax | Indicates the fax |
| Email | Indicates the email |
| Unique Number | Indicates the unique number |
| Account Opening Date | Indicates the account opening date |
| Alternate Account Number | Indicates the alternate account number |

35.9 Activity Journal Report

This report gives details about activity journal in 'Core Activity Journal' screen. To invoke this screen, type 'CSRPACTJ' in the field at the top right corner of the Application tool bar and

clicking the adjoining arrow button.

Core Activity Journal

From Date To Date

Report For

Type ☒ All Modules ☐ Selected Modules

Report

1 Of 1

| Module |
|--------------------------|
| <input type="checkbox"/> |

Report Format PDF Report Output Print

Printer At Client Printer

Ok Exit

From Date

Specify the start date of the report date range. The system will include the details of the record from this date.

To Date

Specify the end date of the report date range. The system will include the details of the record until this date.

Report For

Specify whether you want to generate the report for all the modules or selected modules alone. If you select 'Selected Modules', you need to specify the modules below.

Module

If you need to generate the report for selected modules, you need to indicate the modules here. Use the add button to add more modules.

35.9.1 Contents of Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report, the date and time at which it was generated and the modules covered in the report.

Body

You can find the following details in the body of the report:

| Field Name | Field Description |
|--------------|-------------------------------------------------------------|
| Module | The module for which the report is being generated |
| Product Type | The type of product for which the report is being generated |

| | |
|--------------------|------------------------------------------------------|
| Contract Ref No | The reference number of the contract being reported |
| Counter Party No | The CIF ID of the customer involved |
| Counter Party Name | This is the name of the customer involved |
| User Def. Status | The status if the user defined elements |
| Event Date | The date on which the event took place |
| Seq. No | The sequence number of the event |
| Event Description | The description of the event |
| Contract Status | The status of the contract i.e., active, closed etc. |
| Maker ID | The identification number of the maker |
| Checker ID | the identification number of the checker |
| Reversed Seq. No. | The reversed sequence number |

35.10 Core Exception Report

This report gives details about core exception in 'Core Exception' screen. To invoke this screen, type 'CSRPEXCP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen is as shown below:

From Date

Specify the start date of the report date range. The system will include the details of the record from this date.

To Date

Specify the end date of the report date range. The system will include the details of the record until this date.

Report For

Specify whether you want to generate the report for all the modules or selected modules alone. If you select 'Selected Modules', you need to specify the modules below.

Selected List

If you need to generate the report for selected modules, you need to indicate the modules here. Use the add button to add more modules.

35.10.1 Contents of Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The Header carries the title of the report, information on the branch code, the branch date, the ID of the user who generated the report, the date and time at which it was generated and the modules covered in the report.

Body

You can find the following details in the body of the report:

| Field Name | Field Description |
|--------------------|-----------------------------------------------------|
| Module | The module for which the report is being generated |
| Contract Ref No | The reference number of the contract being reported |
| Counter Party | The name of the counter party |
| Counter Party Name | The name of the counter party involved |
| Event Description | The description of the event |
| Exception | The description about the exception |

35.11 Uncollected Funds Report

This report provides details of uncollected funds based on release date of the fund'. You can invoke this screen by typing 'ACRUNCOL' in the field at the top right corner of the application tool bar and clicking the adjoining arrow button.

Uncollected Funds Print

Accounts ☒ All ☐ One

Date ☒ Present Date ☐ Between Dates

From Date

To Date

Report Format PDF

Report Output Print

Printer At Client

Printer

Ok Exit

Specify the following details.

Accounts

Select the account for which the report is to be generated. The options are:

- All - System fetches all the accounts which has uncollected funds.
- One - If this option is selected, system fetches the report for a particular account, which is selected in the option list.

Date option

Select the date for which report has to be generated:

- Present Date: System fetches the uncollected fund which are available in the current date
- Between dates: If between dates is selected then From date and to date is mandatory. System fetches the Uncollected fund details which are available in between dates.

From Date

Specify the From date.

To Date

Specify the To date.

35.11.1 Contents of Report

Header

The Header carries the title of the Report, information on the branch code, the branch date, the user ID, the module name, the date and time at which the report was generated and the page number of the report.

Body of the report

The details of the uncollected funds that would be displayed in the report are as follows:

| Field Name | Field Description |
|-----------------------|-------------------------------------------------------------------------------------------|
| Account | This is the account for which transaction details is being reported |
| Available Date | This indicates the available date |
| Transaction Reference | This is the reference number of the transaction for which account has uncollected balance |
| Amount | This is the uncollected amount in the account |
| Total Amount | This is the total uncollected amount in the account |

35.12 Account Revaluation Report

This report gives details of the memo revaluation funds. You can invoke this screen by typing 'ACRREVAL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Account Revaluation Report

☒ Memo
☐ Normal

Report Format: PDF
Report Output: Print

Printer At: Client
Printer:

Ok Exit

Memo or Normal

Specify the type of account revaluation report.

35.12.1 Contents of Report

Header

The Header carries the title of the Report, information on the branch code, the branch date, the user ID, the module name, the date and time at which the report was generated and the page number of the report.

Body of the report

The details of the uncollected funds that would be displayed in the report are as follows:

| Field Name | Field Description |
|-------------------------------------|---------------------------------------------------------------------------|
| Currency | This is the currency for which transaction details is being reported |
| Revaluation Rate | This is the revaluation rate |
| Account | This is the account for which transaction details is being reported |
| Description | This is the description provided |
| Account Revalued | This is the revalued account |
| Account Balance | This indicated the account balance |
| LCY Equivalent (before revaluation) | This indicates the amount equivalent to local currency before revaluation |
| LCY Equivalent (after revaluation) | This indicates the amount equivalent to local currency after revaluation |
| Profit/ Loss | This is the profit or loss incurred |
| Profit/ Loss Amount | This is the profit or loss amount |
| P&L Account | This is the profit or loss account |
| Currency | This is the currency for which transaction details is being reported |
| Rate | This is the revaluation rate |
| Category | This is the GL category |

35.13 Accounts Movement Report

This report gives details of the movement of the accounts for that particular day. You can invoke this screen by typing 'ACRPMOVE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a window titled "Accounts Movement Report". It contains several input fields and radio buttons. On the left, there are "From Date" and "To Date" fields with calendar icons. Below them is a "Single Account" section with "Account No" and "Currency Code" fields. Further down are "Report Format" (set to PDF) and "Report Output" (set to Print) dropdowns. On the right, there are radio buttons for "Value Dated" and "Booking Dated" (selected). Below these are radio buttons for "Single Account" and "All Accounts" (selected). At the bottom right, there are "Printer At" (set to Client) and "Printer" fields. "Ok" and "Cancel" buttons are at the bottom right of the window.

From Date

Specify the From Date from the option list.

To Date

Specify the To Date from the option list.

Account Number

Specify the account number from the option list.

Value Dated

Select if the report is value dated.

Booking Dated

Select if the report is booking dated.

Currency

Specify the currency from the option list.

Account Selection

Specify the type of account selection.

35.13.1 Contents of Report

Header

The Header carries the title of the Report, information on the branch code, the branch date, the user ID, the module name, the date and time at which the report was generated and the page number of the report.

Body of the report

The details of the uncollected funds that would be displayed in the report are as follows:

| Field Name | Field Description |
|------------------------------|-------------------------------------------------------------------|
| Account Number | This is the account number |
| Account Description | This is the brief description for the account |
| Account Currency | This is the currency of the account |
| Opening Balance | This is the opening balance of the account |
| FCY Amount | This is the opening balance of account in FCY |
| LCY Amount | This is the opening balance of account in LCY |
| Transaction Date | This is the transaction date |
| Transaction Description | This is a brief description of the transaction |
| Transaction Reference Number | This is the reference number of the transaction posted to account |
| Value Date | This is the value date of transaction |
| FCY Amount | This is the amount of transaction in Foreign Currency |
| Rate | This is the exchange rate for FCY and LCY |
| LCY Amount | This is the amount of transaction in Local Currency |
| Current Balance | This is the current balance in the account |

35.14 Customer Details Report

This report gives details of the customer and you can generate this report using the 'Customer Details' screen.

You can invoke this screen by typing 'STRCIF' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

35.14.1 Contents of Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The Header carries the branch, information on the branch date, the user ID, the module name, the date and time at which the report was generated and the page number of the report.

Body of the report

The details of the customer information details that would be displayed in the report are as follows:

| Field Name | Description |
|----------------------|---------------------------------------------------------|
| Customer Information | |
| Customer | Customer Identification Number of the customer |
| Customer Name | Customer name |
| Address lines | Displays the address of the customer. |
| Country | The country the customer belongs to. |
| Nationality | The nationality of the customer. |
| Type | Type of the customer (individual or Corporate or Bank). |
| Unique ID Name | Displays the customer's unique id name. |

| | |
|----------------------|---------------------------------------------------------------------------------------------|
| Unique ID Value | Displays the customer's unique id value. |
| Creation Date | Displays the date of customer's number creation. |
| Input By | The Login ID of the user that created the customer record. |
| Input Date and Time | The date the customer record was created. |
| Auth By | The Login ID of the user that has authorized the record. |
| Auth Date and Time | The date of the authorization. |
| Mod Number | Displays the number of times the record was modified. |
| Auth Stat | Displays the current status of the customer record. |
| Record | Displays the record status. |
| Exposure Country | Displays the exposure country details. |
| Frozen | Displays the frozen status of the customer's account. |
| Local Branch | Displays the customer's local branch details. |
| Whereabouts Unknown | Gives the customer's details regarding the whereabouts. |
| Deceased | Indicates whether the customer is fit or deceased. |
| Short Name | Customer's abbreviated name. |
| Liability | This is the customer Liability ID number for which credit facility granted to the customer. |
| Language | Language. |
| Category | Category of the customer of the bank. |
| Professional Details | |
| Designation | Indicates Designation |
| Employer | Indicates Employer |
| Status | Indicates Status |
| Tenure | Indicates Tenure |
| Address | Indicates Address |

| | |
|-----------------------|---------------------------------|
| Email | Indicates Email |
| Fax | Indicates Fax |
| Phone | Indicates Phone |
| Telex | Indicates Telex |
| Home Value | Indicates Home Value |
| Insurance | Indicates Insurance |
| Loans | Indicates Loans |
| Expenses | Indicates Expenses |
| Income | Indicates Income |
| Previous Designation | Indicates Previous Designation |
| Previous Employer | Indicates Previous Employer |
| Rent | Indicates Rent |
| Ret Age | Indicates Ret Age |
| Credit Cards | Indicates Credit Cards |
| IE Currency | Indicates IE Currency |
| Salary | Indicates Salary |
| Corporate Details | |
| National Id | Indicates National Id |
| Name | Indicates Name |
| Currency Of Amounts | Indicates Currency Of Amounts |
| Incorporation Country | Indicates Incorporation Country |
| Incorporation Date | Indicates Incorporation Date |
| Net worth | Indicates Net worth |
| Capital | Indicates Capital |

| | |
|--------------------|------------------------------|
| Registered Address | Indicates Registered Address |
| Address 2 | Indicates Address 2 |
| Address 3 | Indicates Address 3 |
| Country | Indicates Country |
| Business | Indicates Business |
| Director Name | Indicates Director Name |
| Personal Details | |
| Prefix | Indicates Prefix |
| First Named | Indicates First Named |
| Middle Name | Indicates Middle Name |
| Last Name | Indicates Last Name |
| Date Of Birth | Indicates Date Of Birth |
| Sex | Indicates Sex |
| Domicile | Indicates Domicile |
| Line 2 | Indicates Line 2 |
| Line 3 | Indicates Line 3 |
| Domicile Cntry | Indicates Domicile Cntry |
| Minor | Indicates Minor |
| Legal Guard. | Indicates Legal Guard. |
| Passport Number | Indicates Passport Number |
| Issue Date | Indicates Issue Date |
| Expiry Date | Indicates Expiry Date |
| Permanent Address | Indicates Permanent Address |
| Address | Indicates Address |

| | |
|--------------------------|------------------------------------|
| Country | Indicates Country |
| National Id | Indicates National Id |
| Phone | Indicates Phone |
| Telex | Indicates Telex |
| Email | Indicates Email |
| Fax | Indicates Fax |
| Domestic Details | Indicates Domestic Details |
| Accommodation | Indicates Accommodation |
| Dependent Child | Indicates Dependent Child |
| Dependent Other | Indicates Dependent Other |
| Education | Indicates Education |
| Marital Status | Indicates Marital Status |
| Spouse | Indicates Spouse |
| Spouse Employment Status | Indicates Spouse Employment Status |

35.15 Customer Accounts Report

This report gives details of the customer account and you can generate this report using the 'Customer Accounts' screen.

You can invoke this screen by typing 'STRCUSAC' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

35.15.1 Contents of Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The Header carries the branch, information on the branch date, the user ID, the module name, the date and time at which the report was generated and the page number of the report.

Body of the report

The details of the customer accounts details that would be displayed in the report are as follows:

| Field Name | Field Description |
|---------------------|-----------------------------------------------|
| Account Number | Details about customer account Number |
| Account Class | Details about account class |
| Account Description | Account Description |
| Opening Date | The opening date of the account. |
| Dormant | The account status as dormant |
| Frozen | Account status as frozen. |
| No Credits | Gives no credit status of the account number. |
| No Debits | Gives no debit status of the account number. |

| | |
|----------------------------|---------------------------------------------------------------------------------------------------------|
| Stop Payments | Gives the accounts stop pay status. |
| Statement Cycle | Gives the account statement cycle. |
| Statement Day | Gives the account statement day. |
| Statement Type | Gives account statement type. |
| Alternate Account Number | Gives an alternative account number. |
| Branch Code | Gives the branch code. |
| Currency | Currency |
| Customer Number | Gives customer number. |
| Nominee1 | Gives the first nominee details |
| Nominee2 | Gives the second nominee details |
| Account Type | Gives the account type. |
| Dr GL | Gives all debit balances within a specific account class |
| Cr GL | Gives all credit balances within a specific account class. |
| Dr HO Line | In this, all accounts belonging to account class will report, if they move to the status being defined. |
| Cr HO Line | In this, all accounts belonging to account class will report, if they move to the status being defined. |
| Dr CB Line | This is a GL to which all debit accounts belonging to an account class should report to. |
| Cr CB Line | This is a GL to which all credit accounts belonging to an account class should report to. |
| ATM Facility | Availability of ATM facility. |
| Cheque Book Facility | Availability of cheque book facility. |
| Passbook Facility | Availability of passbook facility. |
| Previous Statement Date | Gives the date of the previous statement. |
| Previous Statement Balance | Gives the balance of the previous statement. |
| Previous Statement Number | Gives the number of the previous statement |

| | |
|--------------------------|--------------------------------------------------------------------------------------------------------------------------------------|
| TOD Limit | The temporary overdraft limit facility granted to the customer account |
| Sublimit | It the overdraft facility maximum permitted to this account associated and tracked against the line id maintained for the liability. |
| Limit Currency | Displays the currency code of the limit |
| TOD Limit Start Date | The start date for the temporary overdraft facility |
| TOD Limit End Date | The end date for the temporary overdraft facility. |
| Uncollected Funds Limit | The funds hit the account which are debited / credited to the account with effect from the mentioned value days |
| Line ID | The line code is associated with the liability ID against which the overdraft facility is being tracked. |
| Tanked Status | It is the status of the transaction that hit the account in a specific branch once the branch is marked for EOTI. |
| Account Balance | Gives the total account balance |
| Maker ID | The identification number of the maker |
| Maker Date Stamp | This is the date on which the contract was uploaded. |
| Checker ID | This is the Login ID of the user who authorized the product. |
| Checker Date Stamp | This is the date on which the product was authorized. |
| Mod Number | Displays the number of times the record was modified. |
| Record Stat | Displays the current status of the external account record. |
| Authorization Status | Displays the current authorization status of the record. |
| Joint Holder Code | Displays joint holder CIF ID |
| Joint Holder Description | Displays description of the joint holder |
| Joint Holder | Displays linked entities of the joint holder |

35.16 Document Check List Report

This report gives you the details of the customer account whose documents are pending for submission, expired, or about to expire.

You can invoke this screen by typing 'STRDOCL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Document check list

Branch Code

Document Status

Date Range

From Date

To Date

Report Format

Report Output

Printer At

Printer

Ok Exit

Branch Code

Specify the branch code

Document Status

Specify the status of the document submitted by the customer from the adjoining option list. You can select one of the following:

- Pending
- About to Expire
- Expired

Note

- If you select the document status as 'About to Expire', then the 'From Date' should be greater than the current date.
 - If you select the document status as 'Expired', then the 'To Date' should be less than the current date.
-

From Date

Specify the date from which details should be made available in the report. The system will include all customers whose date is equal to or greater than this date.

To Date

Specify the date till which details should be made available in the report. The system will include all customers whose date is equal to or lesser than this date.

Report Format

Select the format in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- HTML – Select to generate report in HTML format.
- RTF – Select to generate report in RTF format.
- PDF – Select to generate report in PDF format.
- EXCEL – Select to generate report in EXCEL format.

Report Output

Select the report output in which you need to generate the report from the adjoining drop-down list. This list displays the following values:

- Print – Select to print the report.
- View – Select to print the report.
- Spool – Select to spool the report to a specified folder so that you can print it later.

Printer At

Select location where you wish to print the report from the adjoining drop-down list. This list displays the following values:

- Client – Select if you need to print at the client location.
- Server – Select if you need to print at the server location

Printer

Select printer using which you wish to print the report from the adjoining option list.

35.16.1 Contents of the Report**Header**

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report, the date and time at which it was generated and the modules covered in the report.

Body of the Report

| Field Name | Field Description |
|-----------------------------|--------------------------------------|
| Branch Code | Current branch code |
| Customer Number | Customer identification number |
| Customer Name | Customer name |
| Customer Account Number | Customer account number |
| Document Type | Type of document |
| Expiry Date | Expiry date of the document |
| Expected Date of Submission | Expected date of document submission |
| Actual Submission Date | Actual document submission date |

35.17 Memo Revaluation Report

You can invoke this screen by typing 'ACRMREVL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

◆ Memo Revaluation Report

Report Format PDF

Report Output Print

Printer At Client

Printer

Ok Exit

35.17.1 Contents of Report

Header

The Header carries the title of the Report, information on the branch code, the branch date, the user ID, the module name, the date and time at which the report was generated and the page number of the report.


Body of the Report

| Field Name | Field Description |
|-------------------------------|----------------------------------------------------------------------|
| Currency | This is the currency for which transaction details is being reported |
| Revaluation Rate | This is the revaluation rate |
| Account | This is the account for which transaction details is being reported |
| Description | This is the description provided |
| Account Revalued | This is the revalued account |
| Account Balance | This indicated the account balance |
| Lcy Equivalent (before reval) | This indicates the local currency before revaluation |
| Lcy Equivalent (after reval) | This indicates the local currency after revaluation |
| Profit/ Loss | This is the profit or loss incurred |
| Profit/ Loss Amount | This is the profit or loss amount |
| P&L Account | This is the profit or loss account |
| Currency | This is the currency for which transaction details is being reported |
| Rate | This is the revaluation rate |
| Category | This is the category |

35.18 Black Listed During Contract Booking Report

You can invoke 'Black Listed During Contract Booking Report' screen by typing 'CSRPBLCB' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screen is as shown below:



Black Listed During Contract Booking

Date

Report Format

Report Output

Printer At

Printer

Ok Exit

Date

Specify the date when the contract was black listed from the adjoining calendar.

35.18.1 Contents of the Report

The contents of the report are discussed under the following heads:

Header

The header carries the Report Name, Branch, Branch Date, User Id, Module, Run Date and Time.

Body of the Report

| Field Name | Field Description |
|------------------|--------------------------------------------|
| Reference Number | Indicates the reference number |
| Customer Number | Indicates the customer number |
| Customer Name | This indicates the name of the customer |
| Nationality | Indicates the nationality of the customer |
| Unique ID Name | Indicates the unique identification name |
| RM Code | Indicates the relationship manager code |
| RM Name | Indicates the name of relationship manager |

35.19 Black List Report During File Upload Report

You can invoke 'Black List Report During File Upload' screen by typing 'CSRPBLUP' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screen is as shown below:

Black List Report During File Upload

Report Format: PDF
Report Output: Print

Printer At: Client
Printer:

Ok Exit

35.19.1 Contents of the Report

The contents of the report are discussed under the following heads:

Header

The header carries the Report Name, Branch, Branch Date, User Id, Module, Run Date and Time.

Body of the Report

| Field Name | Field Description |
|-----------------|--------------------------------------------|
| Customer Number | Indicates the customer number |
| Customer Name | This indicates the name of the customer |
| Nationality | Indicates the nationality of the customer |
| Unique ID Name | Indicates the unique identification name |
| Unique ID Value | Indicates the unique identification value |
| RM Code | Indicates the relationship manager code |
| RM Name | Indicates the name of relationship manager |

35.20 Cheque Book Issued Report

You can invoke 'Cheque Book Issued Report' screen by typing 'CSRPCHB' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screen is as shown below:

Cheque Book Issued Report

☒ All Branches
☐ Single Branch

Branch

Date Range

From Date
To Date

Report Format
Report Output

Printer At
Printer

Ok Exit

Branch Code

You can generate this report for all the branches or a single branch alone. You can indicate the branch for which the report is being generated using the following options:

- All – If you choose this, the system will generate the report for all the branches.
- Single – If you choose this, you need to specify the branch code for which the report should be generated. The option list displays all valid branch codes maintained in the system. Choose the appropriate one.

Date Range

From Date

Specify a valid date from when you wish to generate the report from the adjoining calendar.

To Date

Specify a valid date till when you wish to generate the report from the adjoining calendar.

35.20.1 Contents of the Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The header carries the Report Name, Branch, Branch Date, User Id, Module, Run Date and Time.

Body of the Report

| Field Name | Field Description |
|-------------------|--------------------------------|
| Date of Issue | Indicates the date of issue |
| Issuing Channel | Indicates the Issuing Channel |
| Account Number | Indicates the account number |
| Account Currency | Indicates the account currency |
| Account Name | Indicates the account name |
| Serial Number | Indicates the serial number |
| Maker ID | Indicates the maker ID |
| Checker ID | Indicates the checker ID |

35.21 Demand Draft Issued Report

You can invoke 'Demand Draft Issued Report' screen by typing 'CSRPDDRP' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screen is as shown below:

Demand Draft Issued Report

☒ All Branches
☐ Single Branch

Branch

Report Format
Report Output

Printer At
Printer

Ok Exit

Branch Code

You can generate this report for all the branches or a single branch alone. You can indicate the branch for which the report is being generated using the following options:

- All – If you choose this, the system will generate the report for all the branches.
- Single – If you choose this, you need to specify the branch code for which the report should be generated. The option list displays all valid branch codes maintained in the system. Choose the appropriate one.

35.21.1 Contents of the Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The header carries the Report Name, Branch, Branch Date, User Id, Module, Run Date and Time.


Body of the Report

| Field Name | Field Description |
|--------------------|-----------------------------------------------------------------------|
| Account Number | Indicates the account number |
| Account Name | This indicates the name of the account |
| Currency | Indicates the currency of the account |
| Amount | Indicates the amount |
| Instrument Number | Indicates the instrument number |
| Description | Indicates the description of the demand draft |
| Cheque Number | Indicates the Cheque Number |
| Drawn On | Indicates the date when the DD was drawn |
| Input On | Indicates the date when the data was provided |
| Reference Number | Indicates the reference number |
| Maker ID | Indicates the identification of the maker of the record |
| Maker Date Stamp | Indicates the date when the record was created |
| Checker ID | Indicates the identification of the checker who authorized the record |
| Checker Date Stamp | Indicates the date on which the record was authorized |

35.22 PDC Input Report

You can invoke 'PDC Input Report' screen by typing 'CSRPPDC' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screen is as shown below:



The screenshot shows a window titled "PDC Input Report". It contains the following controls:

- Report Format: PDF
- Report Output: Print
- Printer At: Client
- Printer: (empty text box)

At the bottom right, there are two buttons: "Ok" and "Exit".

35.22.1 Contents of the Report

The contents of the report are discussed under the following heads:

Header

The header carries the Report Name, Branch, Branch Date, User Id, Module, Run Date and Time.

Body of the Report

| Field Name | Field Description |
|-------------------|---------------------------------------------------------|
| Account Number | Indicates the account number |
| Account Name | This indicates the name of the account |
| Currency | Indicates the currency of the account |
| Amount | Indicates the amount |
| Instrument Number | Indicates the instrument number |
| Bank Name | Indicates the name of the bank |
| Clearing Date | Indicates the date of clearing |
| Value Date | Indicates the value date of the demand draft |
| Maker ID | Indicates the identification of the maker of the record |
| Maker Date Stamp | Indicates the date when the record was created |
| Reference Number | Indicates the reference number |

35.23 Temporary Overdraft Report

You can invoke 'Temporary Overdraft Report' screen by typing 'CSRTEMOD' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button. Temporary overdraft report displays only current and savings account of the customer.

The screen is as shown below:

The screenshot shows a window titled "Temporary Overdraft Report". It has two tabs: "Branch Details" and "Customer".

Branch Details Tab:

- Radio buttons: ☒ All, ☐ Single
- Text field: Branch Code
- Dropdown: Report Format (PDF)
- Dropdown: Report Output (Print)

Customer Tab:

- Radio buttons: ☐ Bank, ☐ Corporate, ☐ Individual, ☒ All
- Dropdown: Printer At (Client)
- Text field: Printer

At the bottom right, there are "Ok" and "Exit" buttons.

Branch Code

You can generate this report for all the branches or a single branch alone. You can indicate the branch for which the report is being generated using the following options:

- All – If you choose this, the system will generate the report for all the branches.
- Single – If you choose this, you need to specify the branch code for which the report should be generated. The option list displays all valid branch codes maintained in the system. Choose the appropriate one.

Customer Type

Select the type of customer from the following options provided:

- Bank
- Corporate
- Individual
- All

35.23.1 Contents of the Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The header carries the Report Name, Branch, Branch Date, User Id, Module, Run Date and Time.


Body of the Report

| Field Name | Field Description |
|-------------------------|---------------------------------------------------------|
| Customer Account Number | Indicates the customer account number |
| Customer Name | This indicates the name of the customer |
| Customer Type | Indicates the type of customer |
| Account Description | Displays the description for the account |
| Branch | Indicates the branch of the account |
| Customer Number | Indicates the customer number |
| Account Class | Indicates the account class of the customer |
| Customer Category | Indicates the category to which customer belong to |
| Currency | Indicates the currency of the account |
| Holding Amount | Indicates the holding amount |
| LCY Opening Balance | Indicates the opening balance in local currency |
| ACY Opening Balance | Indicates the opening balance of the account currency |
| ACY Available Balance | Indicates the available balance of the account currency |
| ACY Current Balance | Indicates the current balance of the account currency |
| Temp OD Since | Indicates the date when the temp OD was started |
| Overdraft Since | Indicates the date when the overdraft was started |
| Temp OD Debits Today | Indicates the day's temp OD debits |
| Temp OD Credits Today | Indicates the day's temp OD credits |

35.24 Daily Sales Report

You can invoke the screen by typing the code 'CORDSLRP' in the field at the top right corner

of the Application tool bar and click on the adjoining arrow button.



You can specify the following parameters here:

Branch Code

Specify the branch code from the adjoining option list.

From Date

Specify a valid date from when you wish to generate the report from the adjoining calendar.

To Date

Specify a valid date till when you wish to generate the report from the adjoining calendar.

35.24.1 Contents of the Report

The parameters specified while generating the report are printed at the beginning of the report. Other content displayed in the report is as follows:

Header

The following details are displayed in the header section:

| Field Name | Field Description |
|-------------|-----------------------------------------------------------|
| Branch | Indicates Branch Code and Branch Name |
| Branch Date | Indicates Current Date of the Branch |
| User ID | Indicates User ID |
| Date & Time | Indicates the Date and Time when the report was generated |
| Module | Indicates module for which report is generated. |

Body of the Report

The following details are displayed as body of the generated report:

| Field Name | Field Description |
|------------|-------------------|
|------------|-------------------|

| | |
|---------------------|-----------------------------------------|
| Module | Indicates the module code |
| Outstanding Amount | Indicates the outstanding amount |
| Product Code | Indicates the product code |
| Customer ID | Indicates the customer ID |
| Customer Name | Indicates the name of the customer |
| Product Description | Indicates the product description |
| Account Number | Indicates Customer Account number |
| Booking Date | Indicates the date of booking |
| Branch Name | Indicates Branch Name |
| RM Code | Indicates the relationship manager code |
| DS Code | Indicates the DS code |

35.25 Exception Report

The report gives details of overrides accepted during transaction processing.(for example, Available Balance * for * is less than the Min balance for the A/c Class, Signature Verification not done, etc. You can specify the period for which you require the report when you invoke the report function. In the Application Browser, this report is available under the Signature Verification module.

To invoke this screen type 'SVROV' in the field at top right corner of the Application tool bar and click the adjoining arrow button.

The screenshot shows the 'Exception Report' window. It contains the following elements:

- Module**: Text input field.
- Description**: Text input field.
- All Modules**: Checkmark icon and text.
- Report Format**: Dropdown menu with 'PDF' selected.
- Report Output**: Dropdown menu with 'Print' selected.
- Printer At**: Dropdown menu with 'Client' selected.
- Printer**: Text input field.
- Buttons**: 'Ok' and 'Exit' buttons at the bottom right.

35.25.1 Contents of the Events Log

The contents of this report are discussed under the following heads:

Header

The Header carries the title of the report, information on the branch code, the ID of the user who generated the report, the date and time at which it was generated, the branch date, the modules covered in the report.

Body of the report

The following details are displayed in the report.

| | |
|-----------------------|-----------------------------------------------------|
| Module | The module of the report |
| Contract Reference | The contract reference number of the transaction |
| Event Sequence Number | The sequence number of the event |
| Instrument Code | The instrument code of the transaction |
| User Id | The Id of the user who generates the report |
| Auth Id | The Id of the person who authorized the transaction |
| Exception | Override message |

36. Function ID Glossary

A

| | |
|----------------|-------|
| ACDIBMNT | 9-1 |
| ACRDLTXN | 35-1 |
| ACRJRNAL | 35-4 |
| ACRMREVL | 35-34 |
| ACRPCASH | 35-6 |
| ACRPFVBL | 35-9 |
| ACRPMOVE | 35-22 |
| ACRREVAL | 35-20 |

C

| | |
|----------------|-------|
| CFDCUMRG | 15-3 |
| CORDSLRP | 35-45 |
| CSDACRHM | 5-30 |
| CSDAMLCG | 31-5 |
| CSDAMLLM | 31-4 |
| CSDAMLPC | 31-2 |
| CSDDEMAN | 11-1 |
| CSDDEVDT | 32-1 |
| CSDDEVPR | 32-4 |
| CSDOVDMT | 24-4 |
| CSDPLMNT | 10-24 |
| CSDPXMNT | 14-5 |
| CSDRAMDN | 3-1 |
| CSDSEQGN | 10-27 |
| CSRPACCO | 35-13 |
| CSRPACTJ | 35-15 |
| CSRPBLCB | 35-35 |
| CSRPBLUP | 35-37 |
| CSRPCHB | 35-38 |
| CSRPDDRP | 35-39 |
| CSRPEXCP | 35-17 |
| CSRPPDC | 35-41 |
| CSRTEMOD | 35-43 |
| CSSACRHM | 5-31 |

| | |
|----------------|-------|
| CSSDEVDT | 32-3 |
| CSSDEVPR | 32-6 |
| CYDCCYPR | 13-1 |
| CYDCUSPR | 15-1 |
| CYDRATEE | 14-1 |
| CYRTCURR | 35-10 |
| CYRTHIST | 35-11 |
| CYSRATES | 14-4 |

F

| | |
|----------------|-------|
| FTDVDSRP | 10-12 |
|----------------|-------|

I

| | |
|----------------|-------|
| IADIBMNT | 9-5 |
| ISDINSTN | 10-21 |

L

| | |
|----------------|-------|
| LMDTYPES | 10-23 |
|----------------|-------|

S

| | |
|----------------|-------|
| STDAMTRN | 12-1 |
| STDBANKP | 2-1 |
| STDBRANC | 5-3 |
| STDBRRES | 2-7 |
| STDDATES | 7-1 |
| STDDEALR | 4-1 |
| STDLOCHL | 20-1 |
| STDNETQY | 9-6 |
| STDSTSCD | 17-1 |
| STDTRCOD | 18-1 |
| STDTRNCD | 31-7 |
| STDTXCYL | 5-26 |
| STRCIF | 35-24 |
| STRCUSAC | 35-29 |
| STRDOCL | 35-32 |
| SVROV | 35-47 |