

FCUBS Property File Creation
Oracle FLEXCUBE Universal Banking
Release 12.1.0.0.0
[January] [2016]



Table of Contents

1.	CREATING PROPERTY FILE FOR ORACLE FLEXCUBE UBS	1-1
1.1	INTRODUCTION	1-1
1.2	CREATING PROPERTY FILE	1-1
1.2.1	Setting Oracle FLEXCUBE UBS Plug-ins for Default Installation	1-5
1.2.2	Setting Common Properties for Default Installation	1-6
1.2.3	Setting Email Details for Default Installation	1-8
1.2.4	Setting Report Properties for Default Installation	1-9
1.2.5	Setting BPEL Properties for Default Installation	1-12
1.2.6	Setting BIB Properties	1-14
1.2.7	Saving Property File for Default Installation	1-15
1.2.8	Setting Oracle FLEXCUBE UBS Plug-ins	1-23
1.2.9	Setting Common Properties	1-24
1.2.10	Setting Language Properties	1-30
1.2.11	Setting CSS Style	1-32
1.2.12	Setting Hashing Algorithm Iteration Count	1-32
1.2.13	Setting Email Details	1-33
1.2.14	Setting Report Properties	1-34
1.2.15	Configuring Scheduler	1-36
1.2.16	Setting EMS Properties	1-44
1.2.17	Setting BIP and BIP Advice Report	1-49
1.2.18	Setting GI Upload Properties	1-50
1.2.19	Setting OFTW Details	1-52
1.2.20	Setting Oracle IPM Adapter Properties	1-54
1.2.21	Setting Branch Properties	1-56
1.2.22	Setting BPEL Properties	1-57
1.2.23	Setting BIB Properties	1-59
1.2.24	Setting FCIS UBS Adapter Properties	1-70
1.2.25	Setting ELCM Properties	1-70
1.2.26	Saving Property File	1-71

1. Creating Property File for Oracle FLEXCUBE UBS


1.1 Introduction

This chapter explains the steps to create property file for Oracle FLEXCUBE UBS Application.

1.2 Creating Property File

To create the property file for Oracle FLEXCUBE, follow the steps given below:

1. Launch Oracle FLEXCUBE Universal Banking Solution Installer.



Enter the following details

JDK Path:

Provide Home folder path of JDK1.7

Oracle Home

Provide home folder path of Oracle Client or Database


Application Server Home

Provide home folder path of Application Server


Application Server Location

Select location of the application server either local or remote

2. Click 'Next' and the following screen is displayed.



3. Select 'Universal Banking Solution'.
4. Click 'Next' and the following screen is displayed:



5. Select 'Property File'.
6. Specify the following details:

Operating System

Specify the operating system in which you are creating the property file. Select the appropriate one from the adjoining drop-down list.

Application Server


Specify the application server in which you are creating the property file. Select the appropriate one from the adjoining drop-down list.

Release

Specify the release in which you are creating the property file. **Select** the appropriate one from the adjoining drop-down list. The options are:

KERNEL
VN.Cluster

7. Once you have specified the details, click 'Next' to continue and following screen is displayed:



8. In this screen, choose either Default or Custom installation.


Default – Only the minimum list of details are asked for. Insulation plug-in is de-selected. SSO is by default No.

If there are any issues with the default values then, the property file created can be loaded and choosing custom Installation option it can be corrected.

Default makes sense if the user is acquainted with flexcube configuration defaults else its advised to go with custom installation.

a.Default Installation:

After selecting Default Installation, Click 'Next' ,the following will be displayed




Click 'Centralized' option which is the only applicable for Default Installation and click next.

1.2.1 Setting Oracle FLEXCUBE UBS Plug-ins for Default Installation

This section describes the process of setting plug-ins.

1. You can select the plug-ins from the following screen.



2. You need to select the plug-ins to be included in the installation. Check the box against the required plug-ins. The following plug-ins are available for Oracle FLEXCUBE:

Branch

BPEL

Bank in a Box

OFTW

Insulation

ELCM


Note: DMS, REPORTS, SCHEDULER are selected by default. SCHEDULER is embedded in default mode.

3. Once you have selected the plug-ins, click 'Next' and the 'Common Properties' screen appears.

1.2.2 Setting Common Properties for Default Installation

This section describes the process of setting common properties of Oracle FLEXCUBE.

4. The installer displays the 'Common Properties' screen.



5. Specify the following details:

Debug Logs Required

If you require debug option, select 'Yes' from the drop-down list. If you do not require debug option, select 'No'.

Work Area

Specify the work area.

For example: D:\BrnDbgs\

Signature Path

Specify the location at which the signature images are placed.

Excel Path


Specify the location at which the excel files are generated.

Click 'Next' and the following screen is displayed:

1.2.3 Setting Email Details for Default Installation

This section describes the method to configure email details.

6. The following screen is displayed:



The screenshot shows the Oracle FLEXCUBE Universal Installer window. The title bar reads "Oracle FLEXCUBE Universal Installer". The main window has a red header bar with "Oracle FLEXCUBE Universal Banking" on the left and the "ORACLE" logo on the right. Below the header, the text "Default Installation" is displayed, followed by "Current screen provides an option for Mail configuring using SMTPS Protocol." A table with three columns: "No.", "Name", and "Value" is shown. The table contains four rows of configuration details. At the bottom of the window, there are four buttons: "Log", "Back", "Next", and "Exit".

No.	Name	Value
1	Host	samplename.mail.com
2	User Id	infra
3	User Password	*****
4	JNDI Name	mail/FCUBSMail

7. Specify the following details.

Host

Specify the SMTP host name.

User ID

Specify the user ID.

User Password

Specify the user password.

JNDI Name


Specify the JNDI name.

8. Once you have specified the above details, click 'Next' and system displays the next screen.

1.2.4 Setting Report Properties for Default Installation

This section describes the methods to set report properties.

9. System displays the following screen:



Oracle FLEXCUBE Universal Banking **ORACLE**

Default Installation
Current screen provides an option for modifying the Oracle BI Publisher properties.

No.	Name	Value
1	Server End Point	http://cvrhp1010:0101/xmlpserver/services/Publi...
2	Name Space	http://xmlns.oracle.com/oxp/service/PublicRepo...
3	User Name	Administrator
4	Password
5	Reports Advice Spool Path	/ReportsSpool
6	Advice Type	NATIVE
7	BIP Server Version	11g
8	BIP Time Zone	IST

Log Back Next Exit

10. Specify the following details:

Server End Point

Specify the BIP end point.

'http://10.10.10.10:1010/xmlpserver/services/PublicReportService_v11'. However, you need to change the IP and port where BIP Application is installed. WSDL URL gets modified based on "BIP Server Version" on selecting the required version from the dropdown.

Name Space

Specify the BIP name space.

By default, the installer displays 'http://xmlns.oracle.com/oxp/service/PublicReportService'.

User Name

Specify the BIP user name. By default, the Installer displays 'Administrator'.

Password

Specify the password for the above user name. By default, the Installer sets it as 'Administrator'.

Reports Spool Path

Specify the reports spool path. By default, the Installer displays D:\.

Advice Type

Specify the advice type. You can choose one of the following:

- NATIVE – This advice type is used for generating advices in text format
- BIP – This advice type is used for generating advices in PDF format.

BIP Server Version

Specify the qualified BIP server version. You can select the appropriate one from the adjoining drop-down list.

BIP Time Zone

Specify the time zone of the BIP server.

11. Once you have specified the above details, click 'Next' and the system displays the next screen.

No.	Name	Value
1	Server	10.10.10.10
2	User id	OFSS
3	Password	*****

12. Specify the following details:

Server

Specify the server IP address for the selected file transfer mode.

User ID

Specify the user ID to access the server of the file transfer mode.

Password

Specify the password to for the above user ID.

13. Click 'Next, the following screen is displayed.

No.	Name	Value
1	Login Service Address	http://10.10.10.10:1010/imaging/ws/LoginService
2	Document Service Ad...	http://10.10.10.10:1010/imaging/ws/DocumentServi...
3	Document Content Se...	http://10.10.10.10:1010/imaging/ws/DocumentCont...
4	IPM User Name
5	IPM Password
6	IPM Application Name	OFSS
7	Http Session Maintain	<input checked="" type="checkbox"/>

Specify the following details:

Login Service Address

This is the endpoint address of the web service (OracleIPM.WebService.EndpointAddress).

Document Service Address

This is the URL to which the Oracle IPM adapter uploads the documents (OracleIPM11G.DocumentService.EndpointAddress).

Document Content Service Address

This is the URL to which the Oracle IPM adapter uploads the documents (OracleIPM11G.DocumentContentService.EndpointAddress).



Note: For websphere application server, the above three service address must end with “?wsdl”

Example for Login Service Address:

WebSphere: <http://10.10.10.10:1010/imaging/ws/LoginService?wsdl>

Weblogic: <http://10.10.10.10:1010/imaging/ws/LoginService>

Similarly, this is applicable for Document Service Address and Document Content Service Address as well.

IPM User Name

This is the user name accessing Oracle IPM (OracleIPM11G.Authentication.UserName).

IPM Password

This is the password for the above IPM user name (OracleIPM11G.Authentication.Password).

IPM Application Name

This indicates the license that provides login rights to Oracle IPM (OracleIPM11G.Application).

HTTP Session Maintain


This checkbox indicates whether HTTP session to be maintained or not (OracleIPM11G.MaintainSession).

14. Once you have specified the above details, click ‘Next’.

1.2.5 Setting BPEL Properties for Default Installation

If you have included BPEL option in the setup, then you need to set the BPEL properties.

15. Set the BPEL properties.



Specify the following details:

Factory Initial

Specify the factory initial.

Provider URL

Specify the URL of the server. Enter the IP address, target server port (AdminServer/ManagedServer) and the context root.

Security Principal

Specify the user name to access the application server where BPEL is installed.

Security Credential

Specify the password for the above user name.

Soa Server Name

Specify the Soa Server Name. By default it will be the Installer sets it to 'default'.

Domain Password

Specify the domain password for which SOA server is extended

Dedicated Connection

Check this box to indicate that this connection is not used for other purposes.

BPEL Realm Name

Specify the BPEL realm name.

BAM URI

Specify the BAM URI.

BPM Installed


Check this box if the BPM is installed.

16. Once you have set the above details, click 'Next'. The following screen is displayed:

1.2.6 Setting BIB Properties

If you have selected Bank in a Box (BIB) plug-in, you need to set the BIB properties.

17. Set the BIB properties.



18. Specify the following details related to Bank in a Box (Siebel CRM integration).

Create Service Request

Specify the URL of the create service request web service.

E.g.: http://10.10.10.10:1010/CreateServiceRequest

Query Service Request

Specify the URL of the query service request web service.

E.g.: `http://10.10.10.10:1010/QueryServiceRequest`

Update Service Request

Specify the URL of the update service request web service.

E.g.: `http://10.10.10.10:1010/UpdateServiceRequest`

Customer Party

Specify the URL of the customer party details web service.

E.g.: `http://10.10.10.10:1010/CustPartyDetails`

Offer Details

Specify the URL of the offer details web service.

E.g.: `http://10.10.10.10:1010/OfferDetails`

Customer Populate

Specify the URL of the customer populate web service.

E.g.: `http://10.10.10.10:1010/CustomerPopulate`

Customer Prospect

Specify the URL of the customer prospect web service.

E.g.: `http://10.10.10.10:1010/CustomerProspect`

Customer KYCFail

Provide the URL of the Customer KYCFail Web Service.

E.g.: `http://10.10.10.10:1010/CustomerKYCFail`


19. Once you have set the above details, click 'Next'.

The following screen is displayed:


1.2.7 Saving Property File for Default Installation

After completing all the required settings explained above, you need to save the property file.


Save the property file.



20. You can view the status of property file creation in the above screen. Once the file is saved, the installer displays the following message:




21. If you do not use the 'Save' or 'Save As' buttons, the installer will save the properties file in '<InstallerSources>\config\PropertyFiles' folder. In that case, you will see the message below.



This completes the properties file creation for default Installation.

b. Custom Installation :

Custom – All details are to be provided.



22. Select the type of application deployment. You can choose one of the following options:

Centralized

Select this if you require centralized installation.

Decentralized

Select this if you require decentralized installation. In this case, Installer generates the following files at the end of the build process:

- {Application_name}.ear – This can be deployed as Decentralized Host Application
- {Application_name}.war – This can be deployed as Decentralized Branch Application

Hybrid


Choose this if you require Hybrid Installation. In this case, the Installer generates the following files at the end of the build process:

- {Application_name}.ear - This can be deployed as Centralized Host Application
- {Application_name}.war This can be deployed as Decentralized Branch Application

Note: In Default flow, only Centralised option is available.

23. Click 'Next'. Based on the application deployment type selected, the Installer navigates you to the appropriate screen. See the following steps for details.

24. In case of centralized deployment, the following screen is displayed:




25. Specify the following details:

Centralized Property File

The property file needs to be built before the EAR file. If you are creating a new property file, leave the field blank. If you wish to modify an existing property file, you can manually specify the location of the property file.

26. In case of decentralized deployment, the following screen is displayed:



27. Specify the following details:

Operating System:

Specify the operating system for decentralized installation.

Version:

Specify the version of the operating system for decentralized installation.


Application Server

Specify the application server for decentralized installation.

Version


Specify the version of the application server for decentralized installation.

28. Click 'Next' and the following screen is displayed:




29. Specify the following details:


Host Property File

If you are creating a new property file, you can leave this field blank. However, if you wish to modify an existing property file, specify the location. You can use the directory button  to browse and select the directory.

Web Property File

If you are creating a new property file, you can leave this field blank. However, if you wish to modify an existing property file, specify the location. You can use the directory button  to browse and select the directory.

30. In case of **hybrid deployment**, the following screen is displayed:




31. Specify the following details:

Operating System:

Specify the operating system for decentralized installation.


Application Server:

Specify the application server for decentralized installation.




32. Specify the following details:

Centralized Property File

If you are creating a new property file, you can leave this field blank. However, if you wish to modify an existing property file, specify the location. You can use the directory button  to browse and select the directory.

Decentralized Property File

If you are creating a new property file, you can leave this field blank. However, if you wish to modify an existing property file, specify the location. You can use the directory button  to browse and select the directory.

33. Click 'Next' to continue.

1.2.8 Setting Oracle FLEXCUBE UBS Plug-ins

This section describes the process of setting plug-ins.

34. You can select the plug-ins from the following screen.

Plugin Description	Include
Bank In a Box	<input checked="" type="checkbox"/>
Oracle Flexcube Testing Workbench	<input checked="" type="checkbox"/>
Branch	<input checked="" type="checkbox"/>
Reports	<input checked="" type="checkbox"/>
Insulation	<input checked="" type="checkbox"/>
BPEL	<input checked="" type="checkbox"/>

Is Scheduler Standalone ☐

Scheduler URL

35. You need to select the plug-ins to be included in the installation. Check the box against the required plug-ins. The following plug-ins are available for Oracle FLEXCUBE:

- Reports
- Scheduler
- Document Management System
- Branch
- BPEL
- Bank in a Box
- Regression Testing Tool
- Insulation

Note: If scheduler is required then, one can chose if scheduler is required as standalone.

For to choose standalone scheduler, one should go through scheduler option of building the EAR and deploy the EAR ahead of FCIS application

Scheduler URL: The value for the URL should be the scheduler URL that will be available once scheduler application is deployed.



Note the following:

The Installer allows you to set the properties for the selected plug-ins only.

36. Once you have selected the plug-ins, click 'Next' and the 'Common Properties' screen appears.

1.2.9 Setting Common Properties

This section describes the process of setting common properties of Oracle FLEXCUBE.

1. The installer displays the 'Common Properties' screen.

2. Specify the following details:

Debug Logs Required

If you require debug option, select 'Yes' from the drop-down list. If you do not require debug option, select 'No'.

Work Area

Specify the work area.

For example: D:\BrnDbgs\

Signature Path

Specify the location at which the signature images are placed.

Excel Path

Specify the location at which the excel files are generated.

Data Source

Specify the JNDI location. The standard format is 'jdbc/fcjddevDS'.

Request Time Out

Specify the database request timeout value in milli seconds. This is the maximum number of seconds the database waits for a query to return the result.

Connection Time Out

Specify the database connection timeout value in seconds. This is the maximum number of seconds the application waits for a connection to the database to open.

Session Time Out

Enter the session time out value in seconds. This is the maximum number of seconds during which the application gets active without any user intervention. If there is no user intervention continuously for the duration specified here, the user session gets expire.

LOV Fetch Required

If you check this box, the option lists in Oracle FLEXCUBE displays the matching values based on the first characters that you enter in a field. If you specify the first three characters of a value to be entered in an option list and tab out, the system displays the complete list of values that are matching the first three characters.

If you do not check this, option lists does not show the matching values based on the first few characters. You need to specify the complete value against the field.

Click 'Next' and the following screen is displayed:

Max Image Size

Specify the maximum image size that can be uploaded. The default size is 1048576 in bytes.

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Universal Banking ORACLE

Property File Creation
Current screen provides an option for modifying the OBIEE and other property values.

OBIEE ENABLED

OBIEE URL

OBIEE FOLDER

OBIEE SIGNOUT URL

FCM Enabled

FCM URL

OBIEE Enabled

Chose Yes/No from the drop down box

OBIEE URL

Provide OBIEE URL path

OBIEE Folder

Provide a folder path at the application server level

OBIEE Signout URL


Provide OBIEE signout URL

FCM Enabled

Choose Yes/No from drop down box for FlexCube Messaging

FCM URL

Provide FCM application URL if FCM is required



3. Specify the following details:

SSO Required


Check this box to enable single sign-on (SSO). If you check this box, you need to enter the SSO Key.

SSO Key

Specify the SSO key. If you have checked the box 'SSO Required', it is mandatory to specify the SSO key.

If you have checked the box 'SSO Required', the Installer skips the following two screens and directly navigate to the SSL screen shown below in this manual.

If you have not checked the box 'SSO Required', then on clicking the 'Next' button, the following screen is displayed:



External Password Required

Check this box to allow the user-login using MSAD/LDAP password irrespective of the user ID. If you check this box, the user ID can be either the MSAD/LDAP user ID or the FCUBS user ID. And the password can be MSAD/LDAP server password only.


By default, this check box is unchecked. However, you can change this.

If you do not check this box, the installer skips the following screen and directly navigates you to the SSL screen shown below in this manual.

If you check the box, then click 'Next' and the following screen is displayed:

External User Login Required

Check this box to enable user login using MSAD/LDAP user ID. If you check this box, the user can login using MSAD/LDAP server user ID as well as using FCUBS user ID.



If you do not check this box, the user can login using FCUBS user ID only.

By default, this check box is unchecked. However, you can change this.



'Authentication Type' is enabled if one of the above check boxes is checked.

Authentication Type


Select the authentication type from the adjoining drop-down list. This is the type of external server that is used. You can select one of the following options:

MSAD (Microsoft Active Directory)

LDAP (Lightweight Directory Access Protocol)

By default, 'MSAD' is selected; however, you can change it.


Click 'Next' and the following screen is displayed:



4. Specify the following details.

SSL Enabled

Indicate whether SSL is enabled or not. If SSL is required, choose 'Yes'. If SSL is not enabled, the Installer displays the following screen:




It is recommended that you enable SSL.

Click 'Next' and the next screen gets displayed.

1.2.10 Setting Language Properties

This section describes the process of setting language packs of Oracle FLEXCUBE.

1. The system displays the following screen.



2. Specify the following details.

Language

Specify the language in which you wish to see Oracle FLEXCUBE. English is the default language. However, based on the requirement, you can set a different language. Select the appropriate one from the drop-down list.

Based on the language selected, the installer displays the ISO code.

Application Title

Specify the application title.

E.g.: FLEXCUBE UBS

Version

Specify the application version.

E.g.: 12.1.0.0.0

Copy Rights

Specify the copyright details.


E.g.: Copyright@2007-2015 Oracle Financial Software Services Limited. All rights reserved.

3. Once you have specified the details, click 'Next' and the system displays the CSS setting screen.

1.2.11 Setting CSS Style

This section describes the process of setting CSS style.

1. System displays the following screen:



2. Specify the following details:

CSS Style

Specify the CSS style to be used from the adjoining drop down list. You can select one of the following CSS styles:

Default – select this to apply the default style provided along with Oracle FLEXCUBE

Custom – select this to apply a custom style

Name


Specify the name of the CSS style.

3. Once you have specified the above details, click 'Next' and system displays Hashing Algorithm Count Settings screen,

1.2.12 Setting Hashing Algorithm Iteration Count

This section describes the method of setting hashing algorithm iteration count.

1. System displays the following screen:



2. Specify the following details:

Hashing Algorithm Iteration Count

1. Specify the hashing algorithm iteration count. This count implies the time required for logging into the application. An increase in this count increases the login time.


'SYMMETRIC KEY' is the key (exact 24 characters) for all encryption logic.

2. Once you have specified the details, click 'Next' and system displays the next screen.

1.2.13 Setting Email Details

This section describes the method to configure email details.

1. The following screen is displayed:



2. Specify the following details.

Host

Specify the SMTP host name.

User ID

Specify the user ID.

User Password

Specify the user password.

JNDI Name


Specify the JNDI name.

3. Once you have specified the above details, click 'Next' and system displays the next screen.

1.2.14 Setting Report Properties

This section describes the methods to set report properties.

1. System displays the following screen:



2. Specify the following details:

Server End Point

Specify the BIP end point.

'http://10.10.10.10:1010/xmlpserver/services/PublicReportService_v11'. However, you need to change the IP and port where BIP Application is installed. WSDL URL gets modified based on "BIP Server Version" on selecting the required version from the dropdown.

Name Space

Specify the BIP name space.

By default, the installer displays 'http://xmlns.oracle.com/oxp/service/PublicReportService'.

User Name

Specify the BIP user name. By default, the Installer displays 'Administrator'.

Password

Specify the password for the above user name. By default, the Installer sets it as 'Administrator'.

Reports Spool Path

Specify the reports spool path. By default, the Installer displays D:\.

Advice Type

Specify the advice type. You can choose one of the following:

NATIVE – This advice type is used for generating advices in text format

BIP – This advice type is used for generating advices in PDF format.

BIP Server Version

Specify the qualified BIP server version. You can select the appropriate one from the adjoining drop-down list.

BIP Time Zone

Specify the time zone of the BIP server.


3. Once you have specified the above details, click 'Next' and the system displays the next screen.

1.2.15 Configuring Scheduler

If scheduler standalone is chosen during plug-in selection time, all the below screens mentioned under scheduler configuration will not be applicable

This section describes the method to configure scheduler data source.

1. System displays the following screen:



The screenshot shows a window titled "Oracle FLEXCUBE Universal Installer". The main header is "Oracle FLEXCUBE Universal Banking" with the "ORACLE" logo. The section is "Property File Creation" with the text "Current screen provides an option for Scheduler configuration." Below this, there are two input fields: "Scheduler Datasource" with the value "jdbc/fcjSchedulerDS" and "Scheduler Log Rotation Interval" with a dropdown menu set to "WEEKLY". A large text box contains instructions: "Provide the Scheduler Datasource Name in the field Scheduler Datasource." and "Provide the Scheduler Log Rotation Value To move old Scheduler Log to another file at specific time intervals .". At the bottom, there are four buttons: "Log", "Back", "Next", and "Exit".

2. Specify the following details:

Scheduler Datasource

Specify the scheduler datasource which Oracle FLEXCUBE will access.

Scheduler Log Rotation Interval

Select the interval between each rotation of scheduler log.

3. Click 'Next' and the following screen is displayed:

The screenshot shows the 'Oracle FLEXCUBE Universal Installer' window. The title bar says 'Oracle FLEXCUBE Universal Installer'. The main window has a red header with 'Oracle FLEXCUBE Universal Banking' and the 'ORACLE' logo. Below the header, the section is titled 'Property File Creation'. A message states: 'Current screen provides an option for configuring Scheduler Destination Queue.' There are four configuration fields: 'Notify Destination' is a dropdown menu set to 'QUEUE'; 'Queue Name' is a text box containing 'NOTIFY_DEST_QUEUE'; 'Queue Connection Factory' is a text box containing 'NotifyDestQCF' with a 'Secure' checkbox to its right; and 'Notify Queue Location' is a dropdown menu set to 'Internal'. At the bottom of the window are four buttons: 'Log', 'Back', 'Next', and 'Exit'.

4. Specify the following details:

Notify Destination

Specify the notify destination. Select one of the following options:

QUEUE

TOPIC

Queue Name

Set 'NOTIFY_DEST_QUEUE' as the destination queue name.

Queue Connection Factory

Set 'NotifyDestTCF' as the queue connection factory.

Secure

Check this box to indicate that it is a secured queue connection factory. If you check this box, you will be prompted to specify the caller ID and caller password as shown in the following screen.

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Universal Banking ORACLE

Property File Creation

Current screen provides an option for configuring Scheduler Destination Queue.

Notify Destination: QUEUE

Queue Name: NOTIFY_DEST_QUEUE

Queue Connection Factory: NotifyDestQCF ☒ Secure

Caller ID:

Caller Password:

Notify Queue Location: Internal


Log Back Next Exit

Caller ID

Specify the caller ID for the secured queue connection factory.

Caller Password

Specify the password for the caller ID to access the secured queue connection factory.

 If the queue connection factory is not secured, i.e., if you have not checked the box 'Secure', the installer will not display the fields 'Caller ID' and 'Caller Password'. You need not provide these details in that case.

Notify Queue Location

Specify the notify queue location. Select one of the following options:

- Internal
- External



For Oracle WebLogic application server, the notify queue location should be selected as 'Internal'. If you choose 'Internal' as the 'Notify Queue Location', the screen provided in the following step does not get displayed. You will be navigated to next step where you can specify the notify deferred queue name and connection factory.

5. If you choose 'External', system displays the following screen:

The screenshot shows the Oracle FLEXCUBE Universal Installer window. The title bar reads "Oracle FLEXCUBE Universal Installer". The window has a red header bar with "Oracle FLEXCUBE Universal Banking" and the "ORACLE" logo. Below the header, the text "Property File Creation" is displayed, followed by "Current screen provides an option for External Server configuration for Destination Queue." A table with three columns: "No.", "Name", and "Value" is shown. The table contains three rows: 1. "Provide Url" with value "iiop://localhost:1010", 2. "Security Principal" with a masked value "*****", and 3. "Security Credential" with a masked value "*****". Below the table is a large empty rectangular box. At the bottom of the window, there are four buttons: "Log", "Back", "Next", and "Exit".

No.	Name	Value
1	Provide Url	iiop://localhost:1010
2	Security Principal	*****
3	Security Credential	*****

6. Specify the following details of the external queue.

Provider URL

Specify the provide URL (iiop://localhost:1010).

1010 is the default IIOP port.

Security Principal

Specify the login ID to access the application server.

Security Credentials

Specify the password to access the application server.

7. Click 'Next' to proceed with scheduler configuration.



If you choose 'Internal' as the 'Notify Queue Location', you will be directly navigated to the following screen. In that case, the installer will not show the screen explained in the previous step.

Oracle FLEXCUBE Universal Banking

ORACLE

Property File Creation

Current screen provides an option for Scheduler configuration.

Notify Deferred Queue Name: DEFERRED_DEST_QUEUE

Deferred Queue Connection Factory: DeferredDestQCF ☐ Secure

Log Back Next Exit

8. Specify the following details:

Notify Deferred Queue Name

Set 'DEFERRED_DEST_QUEUE' as the notify deferred queue name.

Deferred Queue Connection Factory

Set 'DeferredDestQcf' as the deferred queue connection factory.

Secure

Check this box to indicate that it is a secured deferred queue connection factory. If you check this box, you will be prompted to enter the caller ID and caller password as shown in the following screen.

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Universal Banking **ORACLE**

Property File Creation

Current screen provides an option for Scheduler configuration.

Notify Deferred Queue Name

Deferred Queue Connection Factory ☒ Secure

Caller ID

Caller Password

Log Back Next Exit

9. Specify the caller ID and caller password for the secured deferred queue connection factory.
10. Click 'Next' and the following screen is displayed:

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Universal Banking **ORACLE**

Property File Creation

Current screen provides an option for Scheduler Notify Internal Queue configuration.

Notify Queue Name

Dead Letter Queue Name

Notify Queue Connection Factory ☐ Secure

Log Back Next Exit

11. Specify the following details:

Notify Queue Name

Set 'NOTIFY_QUEUE' as the notify queue name.

Dead Letter Queue Name

Set 'NOTIFY_QUEUE DLQ' as the dead letter queue name.

Notify Queue Connection Factory

Set 'NOTIFY_MDB_QCF' as the notify queue connection factory.

Secure

Check this box to indicate that it is a secured queue connection factory. If you check this box, you will be prompted to enter the caller ID and caller password as shown in the following screen.

The screenshot shows a window titled "Oracle FLEXCUBE Universal Installer". The main header is "Oracle FLEXCUBE Universal Banking" with the ORACLE logo. The section is "Property File Creation". Below the header, it says "Current screen provides an option for Scheduler Notify Internal Queue configuration." The form contains the following fields and controls:

Notify Queue Name	NOTIFY_QUEUE
Dead Letter Queue Name	NOTIFY_QUEUE_DLQ
Notify Queue Connection Factory	NOTIFY_MDB_QCF
	<input checked="" type="checkbox"/> Secure
Caller ID	
Caller Password	

At the bottom, there are four buttons: "Log", "Back", "Next", and "Exit".

12. Specify the caller ID and caller password for the secured notify queue connection factory.

13. Click 'Next' and the following screen is displayed:

Oracle FLEXCUBE Universal Banking **ORACLE**

Property File Creation
Current screen provides an option for Scheduler EMS Queue configuring.

No.	Name	Value
1	Incoming Dead Letter Queue Name	EMS_QUEUE_DLQ
2	Incoming backup Queue Name	EMS_QUEUE_BACK
3	Incoming Queue Connection Factory	EmsQcf
4	Secure Incoming Queue Connection	<input type="checkbox"/>
5	Incoming Queue Caller Id	
6	Incoming Queue Caller Password	
7	Outgoing Dead Letter Queue Name	EMS_QUEUE_DLQ
8	Outgoing Queue Connection Factory	EmsQcf

Log Back Next Exit

Specify the following details:

Incoming Dead Letter Queue Name

Set 'EMS_QUEUE_DLQ' as the incoming dead letter queue name.

Incoming Backup Queue Name

Set 'EMS_QUEUE_BACK' as the incoming backup queue name.

Incoming Queue Connection Factory

Set 'EmsQcf' as the incoming queue connection factory.

Secure Incoming Queue Connection

Check this box to indicate that it is a secured queue connection.

Incoming Queue Caller ID

Specify the caller ID for the secured queue connection.

Incoming Queue Caller Password

Specify the caller password for the secured queue connection.

Outgoing Dead Letter Queue Name

Set 'EMS_QUEUE_DLQ' as outgoing dead letter queue name.

Outgoing Queue Connection Factory

Set 'EmsQcf' as the outgoing queue connection factory.

Secure Outgoing Queue Connection

Check this box to indicate that it is a secured outgoing queue connection.

Outgoing Queue Caller ID

Specify the caller ID for the secured queue connection.

Outgoing Queue Caller Password

Specify the caller Password for the secured queue connection.

Outgoing Queue Provider URL

Specify the URL of the outgoing queue.

Queue Principal

Specify the queue principal.

Queue Credential

Specify the queue credential.

Incoming Queue Name

Specify the incoming queue name.

Outgoing Queue Name

Specify the outgoing queue name.

SFMS Incoming Queue

Specify the SFMS Incoming Queue.

RTGS Incoming Queue

Specify the RTGS incoming Queue.

Once you have specified the above details, click 'Next' and system displays the next screen.

1.2.16 Setting EMS Properties

You will be navigated to the 'Scheduler EMS Properties' screen. Here, you need to set the EMS details.

1. Set the EMS properties:

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Universal Banking ORACLE

Property File Creation
Current screen provides an option for Scheduler EMS Queue configuring.

No.	Name	Value
1	Incoming Dead Letter Queue Name	EMS_QUEUE_DLQ
2	Incoming backup Queue Name	EMS_QUEUE_BACK
3	Incoming Queue Connection Factory	EmsQcf
4	Secure Incoming Queue Connection	<input type="checkbox"/>
5	Incoming Queue Caller Id	
6	Incoming Queue Caller Password	
7	Outgoing Dead Letter Queue Name	EMS_QUEUE_DLQ
8	Outgoing Queue Connection Factory	EmsQcf

Log Back Next Exit

2. Specify the following details:

OutGoing Connection Factory

Specify the name of the outgoing connection factory to which EMS listens. You need to create this connection factory at the application server.

For details on connection factory creation, follow the steps described for creation of notify connection factories.

Incoming Connection Factory

Specify the name of the incoming connection factory to which EMS listens. You need to create this connection factory at the application server.

For details on connection factory creation, follow the steps described for creation of notify connection factories.

Outgoing Queue Name

Specify the name of the outgoing queue for which EMS is configured. By default, this is set as 'NOTIFY_QUEUE_DLQ'.

Incoming Queue Name

Specify the name of the incoming queue for which EMS is configured. By default, this is set as 'NOTIFY_QUEUE_DLQ'.

Incoming Backup Queue Name

Specify the name of the incoming backup queue for which EMS is configured.

Outgoing Queue Provider URL

In case EMS OUT MDB is to be configured to queue, you need to specify the URL for outgoing provider based on the application server. By default, the Installer displays the outgoing queue provider URL for Oracle WebLogic.

This value is application server dependent.

The details of Outgoing Queue Provider URL to be used for different application servers are given below:

Application Server	EMS Out Initial Context Factory
Oracle WebLogic	t3://<ip_adress>:port E.g.: t3://10.10.10.10:1010 Here, 10.10.10.10 represents the local host and 1010 to the target server default port (AdminServer/ManagedServer).
IBM WebSphere	iiop://<ip_adress>:port E.g.: iiop://10.10.10.10:1010 Here, 1010 represents the default iiop port

Queue Principal

If EMS OUT MDB has to be configured to queue, you need to specify the EMS out queue principal. This is the user name for the application server in which the queue is configured.

Queue Credential

If EMS OUT MDB has to be configured to queue, you need to specify the EMS out queue credential. This is the password for the above user name created for application server in which the queue configured.

3. Once you have specified the above details, click 'Next' and the following screen is displayed:

Property File Creation
Current screen provides an option for Scheduler EMS FTP/FTPS configuring.

No.	Name	Value
1	File TranferMode FTPS	FTPS
2	Server	10.10.10.10
3	User id	OFSS
4	Password	*****
5	File Type	.txt
6	Swift Format	1
7	Swift Message Delimiter	<input checked="" type="checkbox"/>
8	Swift Message Terminator	<input checked="" type="checkbox"/>

Log Back Next Exit

4. Specify the following details:

File Transfer Mode FTPS

Specify the mode of transferring files to EMS. Select one of the following:

FTPS
SFTP
HTTP

Server

Specify the server IP address for the selected file transfer mode.

User ID

Specify the user ID to access the server of the file transfer mode.

Password

Specify the password to for the above user ID.

File Type

Specify the type of file that is transferred. By default, the Installer sets it as '.txt'.

SWIFT Message Delimiter

Specify the character which is used as the message delimiter.

SWIFT Message Terminator

Specify the character which is used as the message terminator.

- Once you have specified the above details, click 'Next'. and the following screen is displayed:

The screenshot shows a window titled "Oracle FLEXCUBE Universal Installer". The main header is "Oracle FLEXCUBE Universal Banking" with the "ORACLE" logo. Below this, the text "Property File Creation" and "EMS -Structured Financial Messaging System configuration Screen." is displayed. A table with 3 columns: "No.", "Name", and "Value" is shown. The table contains 4 rows of configuration items. Below the table is a large empty text area. At the bottom of the window are four buttons: "Log", "Back", "Next", and "Exit".

No.	Name	Value
1	Signature Block	<input checked="" type="checkbox"/>
2	Keystore File Name	/keystore
3	Keystore Alias name
4	keystore Password

- Specify the following details:

Signature Block

Check this box to enable signature block.

Keystore File Name

Specify the keystore file name.

Keystore Alias Name

Specify the keystore alias name.

Keystore Password

Specify the keystore password.

- Once you have specified the above details, click 'Next' and system displays the next screen.

1.2.17 Setting BIP and BIP Advice Report

This screen describes how to create the property file. Here, you need to set the BIP and BIP Advice report details.

1. System displays the following screen:

The screenshot shows the 'Oracle FLEXCUBE Universal Installer' window. The title bar is blue with the Oracle logo. The main window has a red header bar with 'Oracle FLEXCUBE Universal Banking' and the Oracle logo. Below the header, the text 'Property File Creation' is displayed, followed by 'Current screen provides an option for Scheduler BIP and BIP Advice report.' The form contains five input fields: 'Bip Queue Name' with value 'INTERNAL_BIPREPORT_QUEUE', 'Bip DeadLetter Queue Name' with value 'INTERNAL_BIP_QUEUE_DLQ', 'BipAdvice Queue Name' with value 'INTERNAL_BIPADVREPORT_QUEUE', 'BipAdvice DeadLetter Queue Name' with value 'INTERNAL_BIP_ADVICE_QUEUE_DLQ', and 'Queue connection factory' with value 'BIPQCF'. There is a 'Secure' checkbox which is unchecked. At the bottom, there are buttons for 'Log', 'Back', 'Next', and 'Exit'.

2. Specify the following details to set the EMS properties:

BIP Queue Name

Specify the BIP queue name as 'INTERNAL_BIPREPORT_QUEUE'.

BIP DeadLetter Queue Name

Specify the BIP deadletter queue name as 'INTERNAL_BIP_QUEUE_DLQ'.

BIPAdvice Queue Name

Specify the BIP advice queue name as 'INTERNAL_BIPADVREPORT_QUEUE'.

BIPAdvice DeadLetter Queue Name

Specify the BIP advice dead letter queue name as 'INTERNAL_BIP_ADVICE_QUEUE_DLQ'.

Queue Connection Factory

Specify the queue connection factory as 'BIPQCF'.

Secure

Check this box to indicate that it is a secured deffered queue connection factory. If you check this box, you will be prompted to enter the caller ID and caller password as shown in the following screen:

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Universal Banking ORACLE

Property File Creation
Current screen provides an option for Scheduler BIP and BIP Advice report.

Bip Queue Name: INTERNAL_BIPREPORT_QUEUE

Bip DeadLetter Queue Name: INTERNAL_BIP_QUEUE_DLQ

BipAdvice Queue Name: INTERNAL_BIPADVREPORT_QUEUE

BipAdvice DeadLetter Queue Name: INTERNAL_BIP_ADVICE_QUEUE_DLQ

Queue connection factory: BIPQCF ☒ Secure

Caller ID:

Caller password:

Log Back Next Exit

3. Specify the caller ID and caller password for the secured queue connection factory.
4. Once you have specified the above details, click 'Next' and system displays the next screen.

1.2.18 Setting GI Upload Properties

This screen describes how to specify the GI upload property details. Here you need to set the GI Upload properties.

1. System displays the following screen:

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Universal Banking ORACLE

Property File Creation
Current screen provides an queue configuration details for Scheduler GI Upload.

Queue Name: INTERNAL_GI_UPLOAD_QUEUE

Dead Letter Queue Name: INTERNAL_GI_UPLOAD_DLQ

Queue connection factory: GI_UPLOAD_QCF ☐ Secure

Log Back Next Exit

2. Specify the following details:

Queue Name

Specify the queue name as 'INTERNAL_GI_UPLOAD_QUEUE'.

Dead Letter Queue Name

Specify the dead letter queue name as 'INTERNAL_GI_UPLOAD_DLQ'.

Queue Connection Factory

Specify the queue connection factory as 'GI_UPLOAD_QCF'.

Secure

Check this box to indicate that it is a secured deferred queue connection factory. If you check this box, you will be prompted to enter the caller ID and caller password as shown in the following screen:

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Universal Banking ORACLE

Property File Creation

Current screen provides an queue configuration details for Scheduler GI Upload.

Queue Name: INTERNAL_GI_UPLOAD_QUEUE

Dead Letter Queue Name: INTERNAL_GI_UPLOAD_DLQ

Queue connection factory: GI_UPLOAD_QCF ☒ Secure

Caller ID:

Caller Password:

Log Back Next Exit

3. Specify the caller ID and caller password for the secured queue connection factory.
4. Once you have specified the above details, click 'Next' and system displays the next screen.

1.2.19 Setting OFTW Details

1. System displays the following screen:

Oracle FLEXCUBE Universal Banking **ORACLE**

Property File Creation
Current screen provides an option for OFTW Details

No.	Name	Value
1	OFTW Recording Type	REMOTE
2	OFTW User	REMOTE
3	OFTW Password	LOCAL
4	OFTW Provider URL	mail/FCUBSMail

Log Back Next Exit

2. Specify the following details:

OFTW Recording Type

Select the type of recording type, REMOTE/LOCAL from the drop down

OFTW User

Specify the oftw user name

OFTW Password

Specify the oftw password

OFTW Provider URL


Specify URL to OFTW

Note: When OFTW plugin is enabled, it's necessary to have OFTW queue configuration as mentioned in the document "Resource_To_be_Created".

1.2.20 Setting Oracle IPM Adapter Properties

In case you have included DMS in the installation, you need to set the Oracle IPM adapter properties. Navigate to 'Oracle IPM DMS Properties' screen.

1. Set the server type in the following screen.



2. Choose 'Oracle IPM' as the server type.
3. Click 'Next', the following screen is displayed.

No.	Name	Value
1	Login Service Address	http://10.10.10.10:1010/imaging/ws/LoginService
2	Document Service Ad...	http://10.10.10.10:1010/imaging/ws/DocumentServi...
3	Document Content Se...	http://10.10.10.10:1010/imaging/ws/DocumentCont...
4	IPM User Name
5	IPM Password
6	IPM Application Name	OFSS
7	Http Session Maintain	<input checked="" type="checkbox"/>

Specify the following details:

Login Service Address

This is the endpoint address of the web service (OracleIPM.WebService.EndpointAddress).

Document Service Address

This is the URL to which the Oracle IPM adapter uploads the documents (OracleIPM11G.DocumentService.EndpointAddress).

Document Content Service Address

This is the URL to which the Oracle IPM adapter uploads the documents (OracleIPM11G.DocumentConetntService.EndpointAddress).



Note: For websphere application server, the above three service address must end with “?wsdl”

Example for Login Service Address:

Webpsphere: <http://10.10.10.10:1010/imaging/ws/LoginService?wsdl>

Weblogic: <http://10.10.10.10:1010/imaging/ws/LoginService>

Similarly, this is applicable for Document Service Address and Document Content Service Address as well.

IPM User Name

This is the user name accessing Oracle IPM (OracleIPM11G.Authentication.UserName).

IPM Password

This is the password for the above IPM user name (OracleIPM11G.Authentication.Password).

IPM Application Name

This indicates the license that provides login rights to Oracle IPM (OracleIPM11G.Application).

HTTP Session Maintain


This checkbox indicates whether HTTP session to be maintained or not (OracleIPM11G.MaintainSession).

4. Once you have specified the above details, click 'Next'.

1.2.21 Setting Branch Properties

This section describes the branch properties setup.

1. The following screen is displayed.



2. Specify the XA datasource for branch.
3. Click 'Next'. The following screen is displayed.

1.2.22 Setting BPEL Properties

If you have included BPEL option in the setup, then you need to set the BPEL properties.

1. Set the BPEL properties.

No.	Name	Value
1	Factory Initial	weblogic.jndi.WLInitialContextFactory
2	Provide Url	t3://10.10.10.10:0101
3	Security Principal	oc4jadmin
4	Security Credentials
5	Soa Server Name	default
6	Domain Password
7	Dedicated Connection	<input checked="" type="checkbox"/>
8	BPEL Relam Name	FLEXCUBE

Specify the following details:

Factory Initial

Specify the factory initial to obtain an initial context—a reference to a JNDI namespace.

Provider URL

Specify the URL of the server. Enter the IP address, target server port (AdminServer/ManagedServer) and the context root.

Security Principal

Specify the user name to access the application server where BPEL is installed.

Security Credential

Specify the password for the above user name.

Soa Server Name

Specify the Soa Server Name. By default it will be the Installer sets it to 'default'.

Domain Password

Specify the domain password for which SOA server is extended

Dedicated Connection

Check this box to indicate that this connection is not used for other purposes.

BPEL Realm Name

Specify the BPEL realm name.


BAM URI

Specify the BAM URI.

BPM Installed

Check this box if the BPM is installed.

2. Once you have set the above details, click 'Next'. The following screen is displayed:



The screenshot shows a window titled "Oracle FLEXCUBE Universal Installer". The window has a red header bar with "Oracle FLEXCUBE Universal Banking" on the left and the "ORACLE" logo on the right. Below the header, the main content area is titled "Property File Creation" and contains the text "Current screen provides an option for modifying the BPEL Load Balancing properties." Below this text, there are three settings: "Enabling Load Balance" with a checked checkbox, "Frequency" with a text box containing "120", "Task Counts" with a text box containing "5", and "CutOff Time" with a text box containing "13:00". At the bottom of the window, there is a grey bar with four buttons: "Log", "Back", "Next", and "Exit".

Specify the following details:

Enabling Load Balance

Check this box to enable BPEL load balance.

Frequency

Specify the balance load frequency.

Task Counts

Specify the balance load task count.

Cut-off Time


Specify the balance load cut-off time.

3. Once you have specified the above details, click 'Next' and system displays the next screen.

1.2.23 Setting BIB Properties

If you have selected Bank in a Box (BIB) plug-in, you need to set the BIB properties.

1. Set the BIB properties.



The screenshot shows the Oracle FLEXCUBE Universal Installer window. The title bar reads "Oracle FLEXCUBE Universal Installer". The main window has a red header bar with "Oracle FLEXCUBE Universal Banking" and the "ORACLE" logo. Below the header, the text "Property File Creation" is displayed, followed by "Current screen provides an option for BIB configuration." A table with 3 columns (No., Name, Value) lists 8 properties. At the bottom, there are buttons for "Log", "Back", "Next", and "Exit".

No.	Name	Value
1	Create Service Request	http://10.10.10.10:1010/CreateServiceRequest
2	Query Service Request	http://10.10.10.10:1010/QueryServiceRequest
3	Update Service Request	http://10.10.10.10:1010/UpdateServiceRequest
4	Customer Party	http://10.10.10.10:1010/CustPartyDetails
5	Offer Details	http://10.10.10.10:1010/OfferDetails
6	Customer Populate	http://10.10.10.10:1010/CustomerPopulate
7	Customer Prospect	http://10.10.10.10:1010/CustomerProspect
8	Customer KYC Fail	http://10.10.10.10:1010/CustomerKYCFail

2. Specify the following details related to Bank in a Box (Siebel CRM integration).

Create Service Request

Specify the URL of the create service request web service.

E.g.: `http://10.10.10.10:1010/CreateServiceRequest`

Query Service Request

Specify the URL of the query service request web service.

E.g.: `http://10.10.10.10:1010/QueryServiceRequest`

Update Service Request

Specify the URL of the update service request web service.

E.g.: `http://10.10.10.10:1010/UpdateServiceRequest`

Customer Party

Specify the URL of the customer party details web service.

E.g.: `http://10.10.10.10:1010/CustPartyDetails`

Offer Details

Specify the URL of the offer details web service.

E.g.: `http://10.10.10.10:1010/OfferDetails`

Customer Populate

Specify the URL of the customer populate web service.

E.g.: `http://10.10.10.10:1010/CustomerPopulate`

Customer Prospect

Specify the URL of the customer prospect web service.

E.g.: `http://10.10.10.10:1010/CustomerProspect`


Customer KYCFail

Provide the URL of the Customer KYCFail Web Service.

E.g.: `http://10.10.10.10:1010/CustomerKYCFail`

3. Once you have set the above details, click 'Next'.

The following screen is displayed:



4. Specify the following details:

Date Format

Specify the format in which the date should be displayed.

Date Separator

Specify the date separator symbol. This symbol will be used to separate date, month and year.

Workflow Frequency

Specify the workflow frequency.

Compress Request


Check this box to compress request.

Compress Response

Check this box to compress responses.

5. Once you have specified these details, click 'Next'.

6. If you are deploying the application in decentralized mode, the installer displays the following screen:



7. Specify/modify the following decentralised property values.

Work Area

Specify the path of the work area

Host Server URL

Specify the URL of the host server.

Image File Path

Specify the path where the image has to be stored.

Image file format:

Specify the format of the image file, for example, JPG.


Online Pooling Frequency

Specify the online pooling frequency in seconds.

Untank Pooling Frequency

Specify the untank polling frequency in seconds.

8. Once you have specified these details, click 'Next' and the following screen is displayed:



9. Specify the following SSO details for the branch:

SSO Required


Check this box to enable single sign-on (SSO).



If you check this box, you need to enter the SSO Key.

SSO Key

Specify the SSO key.



If you have checked the box 'SSO Required', you need to specify the SSO key.

10. If you have checked the box 'SSO Required', the Installer will skip the following two screens and directly navigate to the SSL screen shown below in this manual.

If you have not checked the box 'SSO Required', then there is a need to update following details.

External Password Required

Check this box to allow user login using MSAD/LDAP password irrespective of the user Id.



If you check this box, the user can login using MSAD/LDAP server password only. The user Id can be one of the following:

MSAD/LDAP user Id

FCUBS user Id

If you do not check this box, then the installer skips the following screen and directly navigates to the SSL screen shown below in this manual.

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Universal Banking ORACLE

Property File Creation

Current screen provides an option for Enabling Single Sign on

SSO Required ☐

SSO KEY

Authentication details maintained external to FLEXCUBE

External Password Required ☒ Authentication Type MSAD ▼

External User Login Required ☐


MSAD
MSAD
LDAP


Single sign-on (SSO) is a property of access control of multiple related, but independent software systems. With this property a user logs in once and gains access to all systems without being prompted to log in again at each of them. Conversely, Single sign-off is the property whereby a single action of signing out terminates access to multiple software systems. This screen provides an option for External Authentication. If External Authentication is not required

Log Back Next Exit

External User Login Required

Check this box to enable user login using MSAD/LDAP user Id.

 If you check this box, the user can login with MSAD/LDAP server user Id as well as FCUBS user Id. If you do not check this box, the user can login using FCUBS user Id only.



Authentication Type

Select the authentication type. This is the type of external server that is used. You can select one of the following options:

MSAD (Microsoft Active Directory)

LDAP (Lightweight Directory Access Protocol)

The default option is MSAD; however, you can change it.

11. If you check the box, then the installer navigates to the following screen on clicking 'Next' button.

Oracle FLEXCUBE Universal Installer

Oracle FLEXCUBE Universal Banking **ORACLE**

Property File Creation
LDAP Server Details for Branch

No.	Name	Value
1	LDAP SERVER URL	LDAP://10.10.10.10:111
2	LDAP SSL ENABLED	<input type="checkbox"/>
3	SECURITY AUTHENTICAT...	Simple
4	DOMAIN NAME	I-FLEX.COM
5	LDAP SERVER TIMEOUT	0

Log Back Next Exit

12. Specify the following details:

LDAP Server URL

Specify the URL to access the LDAP server where the external user Ids or passwords are maintained.

LDAP SSL Enabled

Check this box if the LDAP server is SSL enabled.



If you check this box, then you need to specify the SSL port in the field 'LDAP SERVER URL'.

Security Authentication Type

Depending on the authentication mechanism supported by the LDAP server, you need to select one of the following:

Simple (in most cases)

Strong



Different servers support different authentication mechanisms. By default, the security authentication type is 'Simple'; however, you can change it.

Domain Name

Specify the domain name.

LDAP Server Timeout

Specify the LDAP server timeout in milliseconds.




Note the following:

By default, the LDAP server timeout is zero; however, you can change this.

You must enter a positive integer value. For example, 1000, 10000, 5000, etc.

If the value specified is zero or less, it indicates that no read timeout is specified. Then, the wait for the response infinite until it is received.

13. Once you have specified the above details, click 'Next' and the following screen is displayed:




14. Specify the following details:


SSL Enabled

This check box, if checked, indicates that the SSL is enabled.


15. Once you have specified the above detail, click 'Next'.

The following 'Choose Option' screen is displayed if the check box 'SSL Enabled' is not checked.



 It is recommended that you enable SSL.

16. Once you have selected 'Yes' or 'No', the following screen is displayed:

A screenshot of the "Oracle FLEXCUBE Universal Installer" window. The title bar says "Oracle FLEXCUBE Universal Installer". The window has a red header bar with "Oracle FLEXCUBE Universal Banking" and the "ORACLE" logo. Below the header, it says "Property File Creation" and "Current screen accepts De-Centralized schema Details." There is a table with 3 columns: "SL no", "Name", and "Value". The table contains 5 rows of data. At the bottom, there are four buttons: "Log", "Back", "Next", and "Exit".

SL no	Name	Value
1	User Name	Installer
2	Password	••••••••
3	Connect String	testdb
4	Port No	1521
5	IP Address	10.10.10.10

17. Specify the following details:

User Name

Specify the branch schema user name.

Password

Specify the password to access the branch schema.

Connect String

Specify the connect string.

Port No

Specify the database server port of the branch schema.


IP Address

Specify the database server IP address of the branch schema.

18. Once you have specified the above details, click 'Next' and the next screen is displayed:

1.2.24 Setting FCIS UBS Adapter Properties

This section describes the FCIS UBS Adapter properties setup.




Name	Value
FCUBSAccService Url	htt://10.10.10.10:1111

19. Specify the 'FCUBSAccService Url' and click 'Next' and next screen is displayed.

1.2.25 Setting ELCM Properties

This section describes the ELCM properties setup.

1. Following screen is displayed for ELCM properties.



2. Specify the following details.

Embedding Type

Specify the embedding type. Choose one of the following:

- Normal
- Embed
- Hybrid

Data Sources

Specify the ELCM data source. The standard format is 'jdbc/fcjdevDS'. Notice that the ELCM data source is always the same as the 'Datasource JNDI'.

Include WebServices?

Check this box to include ELCM web services during property file setup.

EI provider URL:


Specify the ELCM provider URL in this text field .

3. Once you have specified the above details, click 'Next' and the next screen is displayed:


1.2.26 Saving Property File

After completing all the required settings explained above, you need to save the property file.


1. Save the property file.



2. You can view the status of property file creation in the above screen. Once the file is saved, the installer displays the following message:



3. If you do not use the 'Save' or 'Save As' buttons, the installer will save the properties file in '<InstallerSources>\config\PropertyFiles' folder. In that case, you will see the message below.



This completes the properties file creation.



FCUBS Property File Creation
[January] [2016]
Version 12.1.0.0.0

Oracle Financial Services Software Limited
Oracle Park
Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:
Phone: +91 22 6718 3000
Fax: +91 22 6718 3001
www.oracle.com/financialservices/

Copyright © [2007], [2016], Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.