

JavaTest™ Harness 4.4

Graphical User Interface User's Guide



Copyright © 2005, 2011, Oracle and / or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related software documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS. Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle America, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and / or its affiliates. Other names may be trademarks of their respective owners.

AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. UNIX is a registered trademark licensed through X/Open Company, Ltd.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Copyright © 2005, 2011, Oracle et / ou ses affiliés. Tous droits réservés.

Ce logiciel et la documentation qui l'accompagne sont protégés par les lois sur la propriété intellectuelle. Ils sont concédés sous licence et soumis à des restrictions d'utilisation et de divulgation. Sauf disposition de votre contrat de licence ou de la loi, vous ne pouvez pas copier, reproduire, traduire, diffuser, modifier, breveter, transmettre, distribuer, exposer, exécuter, publier ou afficher le logiciel, même partiellement, sous quelque forme et par quelque procédé que ce soit. Par ailleurs, il est interdit de procéder à toute ingénierie inverse du logiciel, de le désassembler ou de le décompiler, excepté à des fins d'interopérabilité avec des logiciels tiers ou tel que prescrit par la loi.

Les informations fournies dans ce document sont susceptibles de modification sans préavis. Par ailleurs, Oracle Corporation ne garantit pas qu'elles soient exemptes d'erreurs et vous invite, le cas échéant, à lui en faire part par écrit.

Si ce logiciel, ou la documentation qui l'accompagne, est concédé sous licence au Gouvernement des Etats-Unis, ou à toute entité qui délivre la licence de ce logiciel ou l'utilise pour le compte du Gouvernement des Etats-Unis, la notice suivante s'applique :

U.S. GOVERNMENT RIGHTS. Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle America, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

Ce logiciel ou matériel a été développé pour un usage général dans le cadre d'applications de gestion des informations. Ce logiciel ou matériel n'est pas conçu ni n'est destiné à être utilisé dans des applications à risque, notamment dans des applications pouvant causer des dommages corporels. Si vous utilisez ce logiciel ou matériel dans le cadre d'applications dangereuses, il est de votre responsabilité de prendre toutes les mesures de secours, de sauvegarde, de redondance et autres mesures nécessaires à son utilisation dans des conditions optimales de sécurité. Oracle Corporation et ses affiliés déclinent toute responsabilité quant aux dommages causés par l'utilisation de ce logiciel ou matériel pour ce type d'applications.

Oracle et Java sont des marques déposées d'Oracle Corporation et / ou de ses affiliés. Tout autre nom mentionné peut correspondre à des marques appartenant à d'autres propriétaires qu'Oracle.

AMD, Opteron, le logo AMD et le logo AMD Opteron sont des marques ou des marques déposées d'Advanced Micro Devices. Intel et Intel Xeon sont des marques ou des marques déposées d'Intel Corporation. Toutes les marques SPARC sont utilisées sous licence et sont des marques ou des marques déposées de SPARC International, Inc. UNIX est une marque déposée concédée sous licence par X/Open Company, Ltd.

Ce logiciel ou matériel et la documentation qui l'accompagne peuvent fournir des informations ou des liens donnant accès à des contenus, des produits et des services émanant de tiers. Oracle Corporation et ses affiliés déclinent toute responsabilité ou garantie expresse quant aux contenus, produits ou services émanant de tiers. En aucun cas, Oracle Corporation et ses affiliés ne sauraient être tenus pour responsables des pertes subies, des coûts occasionnés ou des dommages causés par l'accès à des contenus, produits ou services tiers, ou à leur utilisation.

Contents

Preface 11

1. Introduction 1

 GUI Features 1

 Configuration Information 2

 Before Starting the Harness 2

 Starting the Harness 3

 Online User's Guide 3

 Accessing Online Documentation 4

2. Quick Start 5

 Starting a New Test Run 5

 Resuming Work on a Test Run 6

 Browsing the Contents of a Test Suite 7

 Opening a Test Suite 7

 ▼ Open a Test Suite 7

 Opening a Work Directory 8

 Creating a Work Directory 8

 ▼ Create a Work Directory with the Quick Start Wizard 9

 ▼ Create a Work Directory with the Test Manager 9

3. Graphical User Interface 13

- Menus 14
 - File 15
 - Tools 16
 - Windows 17
 - Help 18
 - Setting Preferences 18
 - Appearance Preferences 20
 - Test Manager Preferences 21
- Displaying Online Information 24
 - Help Menu 24
 - Help Buttons 24
 - F1 Key 24
- Keyboard access 25
 - Keyboard Focus 25
 - Keyboard Shortcuts 25
 - Hot Key Shortcuts 25
 - Keyboard Navigation 26
 - Navigation in Hyperlinked Text 27
 - Navigation in Folder Pane Status Tabs 27
 - Navigation in the Test Tree 27
 - Keyboard Activation 28
- Tools 28
 - Agent Monitor Tool 29
 - Report Converter Tool 30
 - Report Converter Window 30
 - Report Converter Menu Bar 31
 - Navigation Bar 32

Report Viewer	32
Report Converter Wizard	32
Test Manager Tool	34
Tasks Performed from the Test Manager	36
Configure Menu	37
Run Tests Menu	38
Report Menu	39
View Menu	39
Tool Bar	40
Progress Monitor	41
Progress Indicator	44
Information Area	45
Test Tree	46
▼ Quick Pick Test Execution of Specific Folders or Tests	52
▼ Refresh Tests and Folders	53
▼ Clear a Test Result	54
▼ Clear Test Results in Folders	54
View Filters	55
▼ Creating a Custom View Filter	60
Work Directory Status Line	64
Test Manager Status Line	64
Configuration Editor	64
Template Editor	72
Log Viewer	80
Test Results Auditor Tool	83
Audit Tool Menu Bar	85
Audit Settings	85
Audit Results	85

4. Configuring a Test Run 91

Creating a Configuration 92

 ▼ Create a New Configuration 92

 ▼ Loading a Configuration 93

 ▼ Editing a Configuration 94

Editing Quick Set Values 95

 ▼ Specifying Tests to Run 96

 Run Tree 97

 Load Test List 98

 ▼ Creating a Test List File 98

 ▼ Using Exclude Lists 99

 Exclude List Selection Options 100

 Latest Exclude List 101

 Other Exclude List 102

 ▼ Specifying Keywords 102

 List of Expressions 104

 List of Logical Operators 104

 ▼ Specifying Prior Status 105

 Prior Status Filter Selections 107

 ▼ Setting Concurrency and Timeout Factor 108

 Concurrency 109

 Time Factor 109

 ▼ Saving a Configuration 110

Using Bookmarks in Configurations 110

 ▼ Set Bookmarks for Specific Questions 110

 ▼ Display Questions With Bookmarks 111

 ▼ Open Groups of Questions 111

- ▼ Clear the Value of a Specific Question 111
- ▼ Remove All Bookmarks 111
- ▼ Remove a Bookmark From a Question 112
- Searching a Configuration 112
 - ▼ Search for Characters in Configurations 112
- Search Criteria 113
- Working with Multiple Configurations 113

5. Creating and Editing Templates 115

- ▼ Creating a Template 116
- Editing a Template 116
 - ▼ Editing in Question Mode 117
 - ▼ Editing in Quick Set Mode 117
 - ▼ Changing Tests to Run 118
- Specifying Tests in the Test Tree 120
 - ▼ Loading a Test List 120
 - ▼ Creating a Test List File 121
 - ▼ Adding or Removing Exclude Lists 122
- Exclude List Pane 123
- Latest Exclude List 124
- Other Exclude List 124
 - ▼ Editing Keywords and Expressions 125
- Keyword Expressions 126
- List of Logical Operators 126
 - ▼ Editing Prior Status Settings 127
- Prior Status Pane 129
 - ▼ Editing Concurrency and Timeout Factor 129
- Concurrency 131
- Time Factor 131

Resolving Configuration-Template Conflicts	133
Setting Bookmarks	134
▼ Set Bookmarks for Specific Questions	135
▼ Display Questions With Bookmarks	135
▼ Open Groups of Questions	135
▼ Close Groups of Questions	136
▼ Clear the Values of All Questions With Bookmarks	136
▼ Clear the Value of a Specific Question	136
▼ Remove All Bookmarks	136
▼ Remove a Bookmark From a Question	136
Using Template Search	137
▼ Loading a Template	138
6. Running Tests	141
Starting a Test Run	142
Monitoring a Test Run	144
Monitoring With a Test Tree	145
Using View Filters	146
Monitoring Output Logs	147
Agent Monitor Tool	148
Stopping a Test Run	149
Troubleshooting a Test Run	149
Test Tree	150
Folder View	150
Test View	150
Log Viewer	151
Service Monitor	151
7. Browsing Test Information	153

Displaying Folder Information	155
Summary Information	156
Status Information	157
Passed	158
Failed	158
Error	159
Not Run	159
Filtered Out	159
Multi-Selection Panel	160
Displaying Test Information	161
Test Description Pane	163
Name	163
Value	163
Files Pane	164
Configuration Pane	164
Name	165
Value	165
Test Run Details Pane	165
Name	165
Value	166
Test Run Messages Pane	167
Message List	167
Message Area	170
Test Result Status Bar	170
Displaying Configuration Information	170
Displaying the Configuration Checklist	171
Viewing Configuration Values	172
Viewing Exclude List Contents	174

Exclude List Contents	174
Test Details	175
Displaying the Question Log	175
Viewing Test Manager Properties	176
Test Suite	177
Work Directory	177
Configuration	177
Plug-Ins	177
Viewing Test Suite Errors	178
8. Creating and Displaying Reports	179
Creating Reports	179
▼ Creating a Test Report	180
HTML Options	183
HTML Files	184
KFL Options in HTML Reports	184
Using a Known Failures List	184
Creating a Known Failures List	185
Specifying a Known Failures List	186
Known Failures List Reports	186
Known Failure Analysis	187
Report Files	189
Displaying Reports	190
▼ Display Reports in the Report Browser	191
Report Browser Contents	197
HTML Report Files	198
Viewing Reports Offline	198
9. Merging and Converting XML Test Reports	199

▼ Merge XML Reports 199

10. Auditing Test Results 203

▼ Audit a Test Run 203

11. Troubleshooting With the GUI 207

Harness Fails During Use 207

Problems Running Tests 208

Tests with Errors 208

Tests that Fail 209

Problems Viewing Test Results 209

Output Overflow Message Displayed in Test Run Messages 210

Problems Viewing Reports 211

Problems Writing Reports 211

Problems Moving Reports 211

12. Glossary 213

Preface

This manual describes how to use the Graphical User Interface (GUI) provided by the JavaTest™ harness (the harness) to run tests of the test suite, browse results, write reports, and audit test results.

The harness provides two User's Guides, the *Graphical User Interface User's Guide* and the *Command-Line Interface User's Guide*. If your test suite uses the JavaTest agent to run tests, the *JavaTest Agent Users' Guide* might also be included.

This User's Guide is also provided by the harness in an online version. The online version of the User's Guide differs from the PDF in the following areas:

- In the online version, all of the harness User's Guides are merged into a single document.
- In the online version, the search function provides a list and ranking of all matching text strings found in the complete harness documentation set.
- The online version can be opened either from the command line in a viewer (without opening the harness GUI) or from within the harness GUI.
- In the online version, hypertext links and navigation bars are used instead of page and section references.

Note – Displaying the online version of the User's Guide does not require the installation of any additional software (such as a web browser). The viewer is provided by the harness.

Security Note

This section discusses potential security vulnerabilities in the harness deliverables.

The harness is a self-contained package and only requires the Java archive (/lib/javatest.jar) to execute.

You can reduce risk by restricting access to optional files or removing them completely. [“Optional Components” on page 12](#) lists portions of the distribution that are not required. Please refer to all the product release notes for the most recent notes about security.

Architects creating test suites should carefully select the set of files to include, and should ensure that file permissions are restricted to essential access.

Optional Components

The harness includes the following optional components:

- Launch scripts are located in each platform’s /bin directory (for example, javatest.ksh or javatest.bat).
Launch scripts are provided for convenience. If you keep the launch scripts, check to ensure that they do not have administrative privileges.
- Documentation is located in the /doc directory.
- Examples or sample code (varies across distributions).
- A test suite might include additional files. Refer to your test suite’s documentation to see which files are optional.

Remote Agent Risks

The harness includes the JavaTest agent, a remote execution framework. Using the agent opens communication ports on your machine and on the agent machine, therefore care is required to ensure that the machine is protected against malicious attack.

For secure operation, both the host and the remote machine should be used in a protected intranet on a physically isolated network.

Before You Read This Book

To fully use the information in this document, you must have a thorough knowledge of the topics discussed in the documentation delivered with your test suite.

How This Book Is Organized

Chapter 1 introduces the harness, describes the basic topics that users should be familiar with before starting the harness on a test system, describes how to start the harness.

Chapter 2 describes the Quick Start process.

Chapter 3 describes the GUI menus, the tools, and operations that can be performed from the harness desktop.

Chapter 4 describes how to create and manage configurations used by the harness to run tests.

Chapter 5 describes how to create and edit templates used .

Chapter 6 describes how to use templates to create configurations.

Chapter 7 describes how to use the Test Manager tool to run tests and monitor results

Chapter 8 describes how to use the Test Manager tool to browse test information.

Chapter 9 describes how to use the Test Manager tool to generate test reports.

Chapter 10 describes how to use the Report Converter tool to merge test reports.

Chapter 11 describes how to use the Test Results Auditor tool to audit test results.

Chapter 12 describes how to use the GUI tools and components to troubleshoot a test run.

Using System Commands

This document does not contain information on basic system commands and procedures such as shutting down the system, booting the system, and configuring devices.

See one or more of the following for this information:

- *Solaris Handbook for Sun Peripherals*
- AnswerBook2™ software online documentation for the Solaris™ operating environment
- Other software documentation that you received with your system

Typographic Conventions

This User's Guide uses the following typographic conventions:

Typeface	Meaning	Examples
AaBbCc123	The names of commands, files, and directories; on-screen computer output	Edit your <code>.login</code> file. Use <code>ls -a</code> to list all files. % You have mail.
AaBbCc123	What you type, when contrasted with on-screen computer output	% su Password:
<i>AaBbCc123</i>	Book titles, new words or terms, words to be emphasized	Read Chapter 6 in the <i>User's Guide</i> . These are called <i>class</i> options. You <i>must</i> be superuser to do this.
	Command-line variable; replace with a real name or value	To delete a file, type <code>rm filename</code> .

Shell Prompts

Examples in this User's Guide contain the following shell prompts:

Shell	Prompt
C shell	<i>machine_name</i> %
C shell superuser	<i>machine_name</i> #
Bourne shell and Korn shell	\$
Bourne shell and Korn shell superuser	#

Related Documentation

The following documentation provides additional detailed information about the harness:

Application	Title
JavaTest harness command-line interface	<i>Command-Line Interface User's Guide</i>
JavaTest agent (optional)	<i>JavaTest Agent User's Guide</i>

Accessing Documentation Online

The Oracle Technology Network enables you to access Java ME technical documentation on the Web:

<http://download.oracle.com/javame/index.html>

We Welcome Your Comments

We are interested in improving our documentation and we welcome your comments and suggestions. Provide feedback at javamedocs_us@oracle.com.

Introduction

The harness provides two interfaces, a Graphical User Interface (GUI) and a command-line interface. The GUI provides a desktop that contains a set of menus and interactive tools that you use to configure and execute tests, control and monitor agents, audit test results, and create reports.

The harness also provides a command-line interface that enables users to accomplish many of the tasks performed in the GUI.

The command-line interface also enables the user to display the online version of the User's Guide without opening the GUI. One means of displaying the online User's Guide (test suites might provide other means) is to type the following command:

```
java -jar testsuite/lib/javatest.jar -onlinehelp
```

In the command line, *testsuite/lib/* represents the location of the directory where the test suite installed the *javatest.jar* file.

See the *Command-Line Interface User's Guide* for a description of the command-line interface.

GUI Features

The features of the GUI include a set of interactive tools and utilities that enable the user to perform the following tasks:

- Configure, run, and monitor tests on a variety of test platforms (such as servers, workstations, browsers, and small devices) with a variety of test execution models (such as API compatibility tests, language tests, compiler tests, and regression tests).
- Evaluate and analyze test results.
- Create template configuration files.

- Generate and view test reports that summarize test runs.
- View the contents of log files.
- Monitor agents (only enabled when the test suite provides an agent). The JavaTest harness supports the use of an agent to run tests on systems that can't run the JavaTest harness.
- Display online user documentation in a viewer that provides context sensitive help, full-text search, and keyword search information.

Configuration Information

The harness uses the Configuration Editor to collect configuration information about how tests are run on a specific test platform. The Configuration Editor saves the information in a configuration file (`.jti` file) that the harness uses to run tests. By using configuration files, the harness can run programs on a variety of Java platforms. The harness writes the test results in the work directory associated with that configuration and test suite. See the Glossary for detailed descriptions of the terms `.jti` file, *work directory*, and *configuration file*.

Before Starting the Harness

Before you start the harness on a test system, you must have a valid test suite and Java Development Kit 6.0 or higher installed on your test system. See your test suite documentation for information about installing the test suite on your test system. Refer to <http://www.oracle.com/products> for information about installing the current Java Development Kit on your test system.

You must also understand how your test group uses or intends to use the harness in its test system. For example, consider the following questions:

- Does your test group use the harness and one or more agents to run distributed tests?

If you use an agent to run tests, you must also install the agent on the platform being tested. If you intend to use the JavaTest agent, see *JavaTest Agent User's Guide* for detailed information about installing the harness agent on a test platform. If you use a custom agent, refer to your test suite documentation for detailed information about installing the agent.
- Does your test group use configuration files and templates from a central location, or does it use individual configuration files customized for each test run?

If your group intends to use configuration files and templates from a central location, the location must be configured for the harness to access the template files.

- Does your test group run the harness from a central location or from local installations in the test system?

If your group uses a central location for the test system, you must be able to access the test system at that location.

Starting the Harness

The harness provides a set of command-line options that you can use to specify the configuration and properties of the GUI when starting the harness. See the *Command-Line Interface User's Guide* for detailed information about command-line options used to specify how the harness starts.

See your test suite documentation for specific information required to start the harness on your test system.

Online User's Guide

The harness also provides an online version of the User's Guide. The online version can either be displayed without starting the harness or from inside the GUI. The online User's Guide merges all of the following PDF User's Guides into one document:

- *Graphical User Interface User's Guide* contains information about using the GUI.
- *Command-Line Interface User's Guide* contains command-line and utility information.
- *JavaTest Agent User's Guide* (available only if supplied by the test suite) contains information about the optional agent.

Throughout the online version, the  icon is used to identify additional information that might be required to fully understand a topic. In the PDF format, this information is presented in the form of notes.

The following sections describe the different actions used to display the online version of the User's Guide and other online documentation.

Accessing Online Documentation

The harness enables you to display the User's Guide and other forms on online documentation without starting the GUI. The viewer is provided by the harness and requires no additional software. To display the online User's Guide, type the following command from the directory containing the `javatest.jar` file:

```
java -jar javatest.jar -onlinehelp
```

You can also display the User's Guide and other forms on online documentation inside the GUI. The following table describes user actions in the GUI that display the User's Guide and other information about the harness.

TABLE 1 Accessing the Online Guide

Action	Description
F1 key	<p>Press the F1 key to display information about the window that has keyboard focus.</p> <p>You must establish keyboard focus in a window before pressing the F1 key. To establish focus, you might have to highlight something in the window.</p>
Help menu	<p>The Help menu lists the following types of online documentation:</p> <ul style="list-style-type: none">Information for the window that has focus. To display information for the window that has focus (such as the Test Manager window), choose <code>window_name</code> from the menu.Information for the harness. To display the User's Guide for the harness, choose JavaTest Harness Online Help from the menu.Optional information (such as, users' guide and release notes) provided by the test suite.Information consists of information about the harness and the virtual machine. This information is collected and provided by the harness.
Help buttons	Click the Help button in a dialog box for information about how to use that dialog box.

Quick Start

The harness includes a Quick Start wizard that enables users to quickly create combinations of test suite, work directory, and configuration files and open them in properly configured Test Manager windows. The harness opens the wizard when one of the following conditions occur:

- The harness cannot restore an existing desktop.
- A user includes a command-line option in the command to start the GUI.
- A user opens a new Test Manager window.

In each case, the wizard enables the user to specify one of the following tasks:

- [Start a New Test Run.](#)
- [Resume Work on a Test Run.](#)
- [Browse the Contents of a Test Suite.](#)

Because each of these tasks has a different set of test suite, work directory, and configuration file requirements, the wizard presents the user with a set of questions that collect the information required for that specified task. When the wizard has collected the required information, it opens a new Test Manager window that is properly set up to perform the specified task.

Starting a New Test Run

The harness requires that you have a test suite, a work directory, and a valid configuration loaded in the Test Manager before running tests. To properly set up the Test Manager, when you choose Start a New Test Run, the wizard displays a series of questions that prompt you to choose the type of configuration used (load a template or create a new configuration), specify a test suite, and choose a work directory. See the following topics for additional information about templates, test suites and work directories:

- [Working With Templates](#)
- [Opening a Test Suite](#)
- [Opening a Work Directory](#)
- [Creating a Work Directory](#)

In the last panel, the wizard displays two options: automatically open the Configuration Editor and automatically begin the test run.

If you choose not to automatically open the Configuration Editor when the wizard closes, the harness displays the Test Manager. In either case, before the harness begins to run tests, it verifies that the configuration is complete. If configuration values are missing or invalid, the harness displays a dialog box describing the problem before opening the Configuration Editor.

See the following topics for additional information about working with configurations:

- [Creating a Configuration](#)
- [Editing a Configuration](#)

Resuming Work on a Test Run

If you choose to resume work on a test run, the wizard only prompts you for the work directory. Because each work directory is mapped to a test suite and a configuration file, you do not provide any additional information to the harness. See [Opening a Work Directory](#) for additional information about using an existing work directory.

In the last panel, the wizard displays two options: automatically open the Configuration Editor and automatically begin the test run.

If you choose not to automatically open the Configuration Editor when the wizard closes, the harness displays the Test Manager. In either case, before the harness begins to run tests, it verifies that the configuration is complete. If configuration values are missing or invalid, the harness displays a dialog box describing the problem before opening the Configuration Editor.

Browsing the Contents of a Test Suite

If you want to view the tests in a test suite without running them, the wizard only requires that you specify the test suite. While the wizard provides you with the option of creating a configuration file for the test suite, this is not required. If you choose not to create a configuration file for the test suite, the harness closes the wizard and opens a Test Manager window containing the test suite.

See [Opening a Test Suite](#) for additional information about loading a test suite.

Note – Until you provide both a work directory and a valid configuration file, you cannot run tests.

Opening a Test Suite

You can open a test suite from either the Test Manager or the Quick Start wizard (if it is enabled and you are starting a new test run).

Note: Some test suites do not implement the optional Quick Start wizard. It won't be available if the test suite architect disabled it.

▼ Open a Test Suite

1. Click the Browse button in the Quick Start wizard Test Suite panel or choose File > Open Test Suite from the Test Manager menu bar.
2. Use the dialog box to navigate to the test suite.
3. Click the test suite icon or enter its name in the text field.
4. Click the Open button.

The harness loads the test suite in a new [Test Manager](#).

Before you can run tests, you must open or create a work directory and load or create a configuration. If you did not use the Quick Start wizard to open the Test Manager, you must perform these operations separately. See the following topics for detailed information about using work directories and configurations:

- [Opening a Work Directory](#) provides information about using an existing work directory for the test run.
- [Creating a Work Directory](#) provides information about creating a new work directory for the test run.
- [Working With Templates](#) provides information about using a template in the test run.
- [Creating a New Configuration](#) provides information about creating a new configuration for the test run.
- [Editing a Configuration](#) provides information about changing configuration values used for the test run.

Opening a Work Directory

Each work directory is associated with a specific test suite, a configuration, and possibly a template. Each time the harness runs tests, it creates test result files that store the information collected during the test run. The harness stores these files in the work directory for all test runs of the test suite with that configuration.

You can open a work directory from either the Quick Start wizard (when resuming work on a test run) or the Test Manager.

Creating a Work Directory

Every work directory is associated with a specific test suite and a configuration file after one is created or opened. Each time the harness runs tests, it creates test result files that store the information collected during the test run. The harness stores these files in the work directory for all test runs of the test suite with that configuration.

You must create a new work directory for each new test suite. You might also choose to create a new work directory to perform multiple test runs of the same test suite but with different configuration files. If you try to use an archive work directory that is no longer considered valid by the harness you must also create a new work directory.

You can create a work directory from either the Test Manager or the Quick Start wizard (if it is enabled and you are starting a new test run). The harness also prompts you to specify a work directory if you begin a task requiring a work directory without having specified one.

▼ Create a Work Directory with the Quick Start Wizard

Note: Some test suites do not implement the optional Quick Start wizard. It won't be available if the test suite architect disabled it.


1. Click the Browse button in the Quick Start wizard Work Directory panel.
The harness displays a Work Directory chooser.
2. Use the chooser to navigate to the location of the new work directory.
3. Enter the name of the work directory in the text field.
4. Click the Create button.
5. Complete the Quick Start wizard.

When you complete the Quick Start wizard, the harness opens a new Test Manager window and creates a work directory for the test suite, template, and configuration file combination.

▼ Create a Work Directory with the Test Manager

1. Choose File > Create Work Directory from the Test Manager menu bar.

The harness displays the Create Work Directory dialog box.



2. Enter the name of the new work directory in the Work Directory Name text field.
3. Click the Browse button and use the File Chooser to select a location for the work directory.

Note – Do not enter the directory name in the file chooser. The harness uses the name from the Work Directory Name text field to create it for you.

Depending on the test suite, the template option might not be allowed (templates not enabled), might be required (cannot select "No Template"), or might be optional (operates as described) in the following step. If you select a template, it will be associated with that work directory for all configurations that are created for that work directory.

4. Use the No Template or Choose a Template buttons to set the template options for the work directory.
5. Check the Launch Configuration Editor box to open the Configuration Editor after the dialog box closes.

6. Click the Create button.

When you create the work directory, the harness opens a new Test Manager window and creates a work directory for the test suite, template, and configuration file combination.

Graphical User Interface

The GUI consists of a desktop containing a set of tools that enable the user to configure and run tests, monitor test status, evaluate and analyze test results, generate reports, view log file contents, and audit test results.

The harness attempts to restore the previous desktop when it displays the GUI. If you used a command-line option (such as, `-newdesktop`) to start the harness or if a previous desktop does not exist, the harness displays the Quick Start wizard. See the *Command-Line Interface User's Guide* for detailed information about using specific values and setup commands in the command line to start the GUI.

The Quick Start wizard guides you through the process of setting up the GUI for a test run. See [Quick Start](#) for information about using the Quick Start wizard.

For detailed information about desktop functions and features, see the following topics:

- [Layout Styles](#)
- [Menus](#)
- [Setting Preferences](#)
- [Displaying Online Information](#)
- [Keyboard access](#)
- [Tools](#)

For information about using desktop tools to perform tasks, see the following topics:

- [Configuring a Test Run](#)
- [Creating and Editing Templates](#)
- [Working with Templates](#)
- [Running Tests](#)
- [Browsing Test Run Information](#)
- [Creating and Displaying Reports](#)
- [Merging and Converting XML Test Reports](#)

- [Auditing Test Results](#)
- [Troubleshooting with the GUI](#)

Menus

The GUI provides two types of menus: desktop and tool. The layout style determines how the menus are displayed in the GUI. The following table describes the two menu types and how the desktop style determines how they are displayed.

TABLE 2 GUI Menus

Menu Type	Description
Desktop	<p>Desktop menus are always available to the user in the desktop menu bar. See GUI Layout for a detailed description of the GUI layout options available to the user. They include the following menus:</p> <ul style="list-style-type: none">• File• Tool• Windows• Help
Tool	<p>These menus are unique to specific tools and are only available to the user when that tool window is open. The appropriate tool menus are merged with the desktop menus in a single menu bar.</p> <p>See Agent Monitor Tool for a description of the Agent Monitor tool menus. If your test suite uses the harness agent, see the <i>JavaTest Harness Agent User's Guide</i> for a description of the Agent Monitor.</p> <p>See Report Converter Tool for a description of the Report Converter tool menus.</p> <p>See Test Manager Tool for a description of the Test Manager tool menus.</p> <p>See Test Results Auditor Tool for a description of the Audit Test Results tool menus.</p>

File

Use the File menu to open files, set user preferences, and exit from the harness. The contents of the File menu change dynamically, based on the context of the desktop. The harness only enables menus when they can be used. The following table describes the contents of the File menu.

TABLE 3 File Menu Contents

Menu Item	Description
Open the Quick Start Wizard	<p>Note: Some test suites do not implement the optional Quick Start wizard. It won't be available if the test suite architect disabled it.</p> <p>Opens the optional Quick Start wizard for you to use for the following tasks:</p> <ul style="list-style-type: none">Start a new test run by selecting a test suite, work directory, and a configuration file. If the configuration file is new or incomplete, the harness opens the Configuration Editor after the wizard closes.Resume work on a previous test run or browse a test suite without running tests.Browse the contents of a test suite.
Create Work Directory	<p>Opens a dialog box that you can use to create a work directory. When you choose to create a new work directory, the harness associates it with the test suite opened in the Test Manager tool window. The harness creates test result files in the work directory that contain all of the information gathered by the harness during test runs of the test suite.</p> <p>See Creating a Work Directory for detailed information about creating a work directory.</p>
Open > Work Directory	<p>Opens a dialog box that you can use to open an existing work directory. Each work directory is associated with a specific test suite and contains information from previous test runs. The test result files in the work directory contain all of the information gathered by the harness during test runs.</p> <p>When you choose to open an existing work directory, the harness performs the following actions:</p> <ul style="list-style-type: none">It associates that work directory with the test suite opened in the Test Manager tool window <i>only</i> if the test suite is both a match and has no other work directory already open.If it cannot associate the work directory with the open test suite, the harness opens a new Test Manager and loads both the work directory and its associated test suite. <p>See Opening a Work Directory for detailed information about opening a work directory.</p>

TABLE 3 File Menu Contents

Open > Test Suite	Opens a dialog box you can use to choose a test suite. When you open the test suite, the harness loads it into new Test Manager. See Opening a Test Suite for additional information.
Recent Work Directory	Displays a list of work directories that have been opened. Choose a work directory from the list to open a new instance of it in the current session.
Preferences	Opens the Preferences dialog box for you to set the display and functional options of the harness. See Setting Preferences for detailed information about setting preferences in the GUI.
Close	Shown in the File menu. Closes the current window without exiting from the harness. Closing a Test Manager closes the work directory.
Exit	Exits from the harness. If you have set your preferences to save your current desktop, your current desktop is saved so that all open windows, test suites, work directories and configurations are restored the next time that you start the harness. See Setting Preferences for detailed information about setting preferences in the GUI.

Tools

The following table describes the tools provided by the harness.

TABLE 4 Tools

Tool	Description
Test Results Auditor	Opens the Test Results Auditor tool that you use to generate and view audit reports of the tests in a work directory.

TABLE 4 Tools

Report Converter	Opens the Report Converter tool that you use to generate and view reports of results from multiple test reports.
Test Manager	Opens the Test Manager tool that you use to do the following tasks: <ul style="list-style-type: none">• Open and create work directories.• Add or modify information that the harness uses when running your tests.• Run the tests of a test suite.• Monitor tests and test results while they are being run.• View test environment settings of your configuration.• View the contents of an exclude list.• Browse completed tests and test results. During a test run, the icons in the Test Manager change to reflect the test status. You can also use the window during and after a test run to browse information about individual tests.
Agent Monitor (Optional)	The Agent Monitor tool is only available for use when the test suite is configured to use an agent. If your test suite includes the JavaTest Harness agent, see the <i>JavaTest Harness Agent User's Guide</i> for detailed information about the agent and the Agent Monitor tool.

Windows

The Windows menu also provides a list of all windows currently open in the harness. You can navigate to any open window by clicking on its name in the list.

Help


Use the Help menu to display user information about the tool window and the harness, the available test suite documentation, version information about the harness, and information about the current Java runtime environment.

TABLE 5 Contents of the Help Menu

Menu Item	Description
<i>Active Window Name</i>	Displays user information about the active window. This menu item is only available in an open tool window.
Online Help	Displays the online version of the harness User's Guide. This version combines the GUI, command-line interface, and the agent User's Guides (when applicable) into one document.
<i>Test Suite Documentation (Optional)</i>	If the test suite provides online documentation, the harness lists it here. Click the document name to display it in the viewer.
About the JavaTest Harness	Displays information about this release of the harness.
About the Java Virtual Machine	Displays information about the runtime used to run the harness.

Setting Preferences

Choose File > Preferences from the menu bar to open the harness preferences dialog. Use this dialog to set the display and functional options of the harness.



The following table describes the contents of the Preferences dialog box.


TABLE 6 Preferences Dialog Box Contents

Preference Category	Description
Appearance	Sets how the desktop displays tool windows and tool tips. See Appearance Preferences for detailed information.
Color Preferences	Sets the color preferences for default input and input status warnings. See Color Preferences for detailed information.
Test Manager	Sets the Test Manager tool bar property. See Test Manager Preferences for detailed information.

Appearance Preferences

Change the desktop appearance by opening the Appearance folder and setting the following options:

- [Tool Tip Options](#)
- [Shutdown Options](#)



See [GUI Layout](#) for a detailed description of the tabbed interface.

Tool Tip Options

You can set the tool tip options from the Appearance category of the Preferences dialog box.

The Tool Tips area contains combo boxes and a check box that you can use to specify how tool tips function in the desktop. The following table describes the available tool tip options.

TABLE 7 Setting Tool Tip Options

Option	Description
Enabled	Use the check-box to enable or disable tool tips for the GUI.
Delay	Use the combo box to select the delay interval before displaying tool tips.
Persistence	Use the combo box to select the duration that the GUI displays a tool tip.

Shutdown Options

Check the Save Desktop State on Exit option to save your current desktop for use in a future test session. This default is on.

When you exit this option saves the current view filter information, recent work directories, and recent configuration information. If a desktop file exists, it will remain.

If you uncheck Save Desktop State on Exit and close the harness, the current view filter information is not saved. The next time you open a test session the harness opens the Quick Start Wizard (if the test suite author has enabled it) or an empty harness tool.

Check Restore Tools State on Start to restore saved desktop settings. The default is on. If this option is not checked, the recent work directories and configuration information are restored but the tools are not.


If Restore Tools is set **on** and Save Desktop State on Exit is set **off**, the harness will always start with one tools set (although **-newdesktop** can be used to remove all data).

Test Manager Preferences

To change the Test Manager preferences, select File > Preferences > Test Manager.

- [Test Manager Preferences](#)
- [Configuration Editor](#)
- [Reporting](#)

The following preferences are set when the Test Manager folder is selected as follows:




- Tool Bar: Check Displayed to see the toolbar. If you enable or disable this option you must restart JavaTest to see the change.



- View Filters: Enables a warning message that is displayed if the [All Tests filter](#) is selected for a test run.
- Test Execution:
- Execution from tree popup includes configuration Test to Run setting:
- Disable sort of Tests to Run when specified from input file: This allows you to set the test execution order. Traditionally tests are run in the order they appear in the main test tree. This order is generally determined by the test suite architect. By selecting this option, the order execution will follow that in the input file for the Tests to Run section in the configuration. That is, the tests will be executed in the order they appear in that file, rather than being sorted and then executed. The default state of this checkbox is unchecked. See
- Test Run Messages: Wrap Test Output in the [Test Run Messages Pane](#).


Configuration Editor

Check the More Info box to view the More Info pane in the configuration editor. Same as choosing View > More Info, except the preference will remain in future sessions.



Reporting

Set the bug prefix URL for KFL reports.



Displaying Online Information

You can display available harness and test suite information in the following ways:

- Help menu
- Help buttons 
- F1 key

Help Menu

The Help menu lists the available harness, test suite, and current runtime information. When multiple test suites are opened, the menu displays a menu item for each document provided by the test suite. Choosing an item from the menu opens it in a separate viewer.

Help Buttons

The desktop provides a help button on all window tool bars and in all dialog boxes. In the tool bar, clicking the help button displays the documentation for that window. In dialog boxes, clicking the help button displays documentation for that dialog box.

F1 Key

Press the F1 key to see detailed information for the window that has keyboard focus. Establish keyboard focus in a window before pressing the F1 key. In some cases, you might have to highlight a component in the window to establish focus.

Keyboard access

The harness uses standard Java programming language key bindings for keyboard traversal and access of the GUI. See the *Java Look and Feel Design Guidelines* at <http://java.sun.com/products/jlf/> for a detailed description of the standard key bindings for keyboard traversal and access of the GUI.

The window or component must have keyboard focus before you can use keyboard navigation, activation, or shortcuts. Keyboard navigation, activation, and shortcut operations are described in the following topics.

Keyboard Focus

When a component has focus, it is generally displayed with a colored border or changes color. However, some components in the GUI cannot be displayed with a focus indicator. In this case, you must continue to use the keyboard to traverse the GUI until focus is displayed.

Keyboard Shortcuts

Keyboard shortcuts perform both navigation and activation in the same action. The following table lists the keys that are used to access menus and online help.

TABLE 8 Keyboard Shortcuts for Navigation and Activation

Activation Keys	GUI Action
F1	Activates the online help.
F10	Activates the File menu.
Shift F10	Activates the pop-up menu if focus is on a folder or test in the test tree.

Hot Key Shortcuts

The harness provides shortcuts throughout the application for accessing menu titles, menu items, text fields, checkboxes, radio buttons, and command buttons.

Shortcut keys are identified in the following ways:

- **Text at the end of tool tips** - For example, Start Running Tests Alt-S

- **Underlined letters in menus and text buttons** - For example, [File](#)
- **Underlined letters in labeled fields** - For example, [Response:](#)

Keyboard Navigation

Keyboard navigation enables you to move keyboard focus from one GUI component to another by using the keyboard without activating the component. The following table lists the keys used for keyboard navigation.

TABLE 9 Keyboard Navigation Keys

Navigation Key	GUI Action
Tab	Navigates to the next focusable component in the GUI. The tab traversal order is generally left to right and top to bottom.
Shift-Tab	Navigates back to the next focusable component.
Control-Tab	Navigates to the next focusable component even if the current component accepts the Tab key as input (such as a text area).
Control-Shift-Tab	Navigates back to the next focusable component even if the current component accepts the Tab key as input (such as a text area).
Left arrow	Moves keyboard focus left one character or component. If focus is in the test tree, focus moves up the tree and closes the node. If focus is on the splitter bar (F8 moves focus to the splitter bar), it moves the splitter bar left.
Right arrow	Moves keyboard focus right one character or component. If focus is in the test tree, focus moves sequentially down the tree, opening the node and traversing all tests in a folder. If focus is on the splitter bar (F8 moves focus to the splitter bar), it moves the splitter bar right.
Up arrow	Moves keyboard focus up one line or component. If focus is in the test tree, focus moves sequentially up the tree but does not open any closed folders. If focus is on the splitter bar (F8 moves focus to the splitter bar), it moves the splitter bar left.
Down arrow	Moves keyboard focus down one line or component. If focus is in the test tree, focus moves sequentially down the tree but does not open any closed folders. If focus is on the splitter bar (F8 moves focus to the splitter bar), it moves the splitter bar right.
Page Up	Navigates up one pane of information within a scroll pane.
Page Down	Navigates down one pane of information within a scroll pane.
Home	Moves to the beginning of the data. In a table, moves to the beginning of a row. If focus is in the test tree, moves to the top of the tree.
End	Moves to the end of the data. In a table, moves to the last cell in a row. If focus is in the test tree, moves to the bottom of the tree.

TABLE 9 Keyboard Navigation Keys

Control-F1	Displays the tool tip information for the GUI object that has focus. Can be used to determine which GUI object has focus.
F6	Shifts focus between left and right panes.
F8	Shifts focus to the splitter bar if focus is in the left or right pane.
Control-T	Shifts focus to the next link in a topic or in a report.
Control-Shift-T	Shifts focus to the previous link in a topic or in a report.

Navigation in Hyperlinked Text

Navigating hyperlinks in text areas such as the More Info pane and report viewer requires that you establish focus in the pane itself. After you have established focus inside the pane, use the keyboard navigation keys listed in Keyboard Navigation to navigate in the pane. Because some components in the GUI cannot display focus, you have to use the keyboard to traverse the GUI until you can determine that focus is established inside the pane.

After focus is established in the pane, use Control-T and Shift-Control-T to navigate to the next and previous link in the document. Use Control and Space bar to select (follow) the hyperlink. See [Keyboard Activation](#) for a list of keys used for keyboard activation.

Navigation in Folder Pane Status Tabs

Navigating in the folder pane test status tabs requires that you establish focus in the pane itself.

After focus is established in the pane, use the Arrow Up and Arrow Down keys listed in Keyboard Navigation to navigate in the pane. When only a single entry is present in the folder pane, you must use the Home or End key to select the item.

Because some components in the GUI cannot be displayed with focus indicators, you may have to use the keyboard to traverse the GUI until you can determine that focus is established inside the folder pane.

Use the Return or Enter key to navigate to the selected item. See [Keyboard Activation](#) for a list of keys used for keyboard activation.

Navigation in the Test Tree

Navigating in a test tree requires that you establish focus in the test tree itself.

After focus is established in the pane, use Arrow Up, Arrow Down, Arrow Left, and Arrow Right keys listed in Keyboard Navigation to navigate in the pane.

Keyboard Activation

After navigating to a component, you can then use the keyboard to activate the component. The following table lists the key that are used to activate GUI components.

TABLE 10 Keyboard Activation

Activation Keys	GUI Action
Enter or Return	Activates the default command button.
Escape	Dismisses a menu or dialog box without changes.
Space Bar	Activates the tool bar button that has keyboard focus.
Shift-Space Bar	Extends the selection of items in a list.
Control-Space Bar	If the item with focus is in a list, it toggles the selection state of the item without affecting any other list selections. If the item is a link, it follows the link.

Tools

The harness provides a set of tools that enable you to perform specific tasks related to running tests, troubleshooting, and reporting test results. The tools provided by the harness include the following:


- [Agent Monitor tool](#) - Enables you to monitor the activity of agents connected to the harness.
- [Report Converter tool](#) - Enables you to merge XML reports from multiple work directories into a single XML report.
- [Test Manager tool](#) - Enables you to perform the following tasks:
 - Load, edit, or create a configuration.
 - Run and monitor tests.

- Browse test results.
- Create and view reports.
- [Test Results Auditor tool](#) - Enables you to audit test results from test runs.

Agent Monitor Tool

If your test suite uses the harness agent, use the Agent Monitor tool to view all agents in a test system that are running tests. Choose Tool > Agent Monitor from the menu bar to open the tool window.


The Agent Monitor window contains two sections: Agent Pool and Agents Currently In Use.



If your test suite uses the harness agent, see the *JavaTest Harness Agent User's Guide* for a detailed description of using the Agent Monitor tool.

Report Converter Tool

You can use the Report Converter tool to merge multiple XML reports created by the JT harness into a single report. To launch the Report Converter tool, choose Tools > Report Converter from the menu bar.




1. [Report Converter window](#)
2. [Report Converter wizard](#)

See [Merging and Converting XML Test Reports](#) for a detailed description of using the Report Converter tool .

Report Converter Window

You can use the Report Converter window to view reports.



1. Report Converter Menu Bar
2. Navigation Bar
3. Report Viewer

Report Converter Menu Bar

The Report Converter menu bar contains a Settings menu. The menu bar also contains harness standard menus. See [Menus](#) for a description of the harness standard menus that are displayed on the menu bar.

The Settings menu contains the following menu items:

- **New** - Launches the Report Converter wizard.

See [Report Converter Wizard](#) for a detailed description.

- **Open** - Launches a file chooser for users to navigate to and open existing reports in the report viewer.

Navigation Bar

The navigation bar contains a report field and navigation buttons. The report field identifies the location and name of the report file displayed in the report viewer. When a report contains hyperlinks to other reports, users can use the links in the report and the navigation buttons to move from page to page.

Report Viewer


The harness displays the report in the viewer. The viewer is a noneditable text area.

Report Converter Wizard

The harness displays the Report Converter wizard when you launch the Report Converter Tool or when you choose Settings > New from the Report Converter Tool menu bar. The Report Converter wizard consists of two panels, an XML Input Files panel and a Report Options panel. See [Merging and Converting XML Test Reports](#) for instructions on the use of the Report Converter wizard.

XML Input Files Panel


Use the XML Input Files panel to specify the harness generated XML files that are to be merged and the directory where the harness is to write the final report.



1. **Report Directory field and Browse button** - Set the directory where the report is saved
2. **Source file fields and Browse buttons** - Specify the source XML report files
3. **Add More button** - Creates additional source file fields
4. **Next button** - Opens the Report Options panel

Report Options Panel

Use the Report Options panel to specify how conflicts between merged reports are handled, choose the report format, and initiate creating the merged report.



1. **Conflict Resolution options** - Determine how conflicts are handled
2. **Report Format Description** - Describes the selected report format
3. **Help button** - Launches a help viewer containing detailed information about the panel
4. **Cancel button** - Closes the Report Converter wizard without taking any action
5. **Create Report button** - Generates the report
6. **Back button** - Returns to the XML Input Files panel
7. **Report Format(s)** - List of available output types

Test Manager Tool


Use the Test Manager tool to load, edit, or create a configuration, to run and monitor tests, to browse test information, and to troubleshoot a test run.

You can launch the Test Manager at any time by choosing Tools > Test Manager or by choosing File > Open Quick Start from the menu bar.

The harness also automatically opens a new Test Manager when you perform one of the following actions:

- Open an existing work directory
- Create a work directory
- Open a test suite

Depending on the layout style that you use, the desktop menus (File, Tools, and Windows) might also be displayed in the menu bar. See [Menus](#) for a description of the desktop menus. See [Appearance Preferences](#) for a description of how to change the layout style.



1. [Configure Menu](#)
2. [Run Tests Menu](#)
3. [Report Menu](#)
4. [View Menu](#)
5. [Tool Bar](#)
6. [Progress Monitor](#)

7. [Progress Indicator](#)
8. [Information Area](#)
9. [Work Directory Status Line](#)
10. [Test Manager Status Line](#)
11. [Test Tree](#)

The Test Manager also provides access to the following items:

- [Configuration Editor](#)
- [Template Editor](#)
- [Log Viewer](#)

Tasks Performed from the Test Manager

The following table describes the tasks that you can perform from the Test Manager.

TABLE 11 Test Manager Tasks

Task	Description
Load, edit, or create a configuration	Provide configuration information required to run your test suite. See Configuring a Test Run for a description of providing a configuration for running tests.
Run tests	Start test runs by choosing the Run Tests > Start menu item or click the  button on the tool bar. See Running Tests for a detailed description of how to run tests.
Monitor test runs	Use the test tree with the folder and test views to monitor the status of the test run. For more information about monitoring test runs, see Monitoring a Test Run .
Browse test information	Use the test tree with the folder and test views to browse information about overall test status as well as what occurred during a test run. See Browsing Test Information for details about browsing test run information.
Create and view test reports	Use the Report menu to create and display reports of test run information. See Creating and Displaying Reports for details about generating and viewing test run information.
Troubleshoot a test run	Use the test tree with the folder and test views to troubleshoot a test run. See Troubleshooting a Test Run for help with troubleshooting test run problems.

Configure Menu

Use the Configure menu to load, create, modify, and view configuration data used for a test run. The following table describes the default menu items in the Configure menu. Because this menu can be customized you might see additional options defined in the current test suite.

The template menu options listed in the following table are only available when template usage is enabled.

TABLE 12 Configure Menu

Menu Item	Description
Edit Configuration	Opens the Configuration Editor and loads the current configuration. The harness uses the Configuration Editor to change configuration values required to run a test suite. See Editing a Configuration for detailed information.
Edit Template	Opens the Template Editor and loads the template on which the current configuration is based. If the test suite disables the template feature, this and all other template menu items are not displayed. This menu item is also disabled when the test suite only enables users to load but not edit templates. Use the Template Editor to change configuration values in the template and to propagate the changes to the current configuration. See Editing a Template for detailed information.
Edit Quick Set	Opens an additional menu containing Tests to Run, Exclude List (optional), Keywords (optional), Environment (optional), Prior Status, Concurrency, and Timeout Factor menu items that you can use to change specific configuration values. See Editing Quick Set Values for detailed information.
New Configuration	Opens the Configuration Editor and loads an empty configuration. The harness uses the Configuration Editor to create configuration data containing the test environment and standard values required to run a test suite. See Creating a Configuration for detailed information.
Load Configuration	Opens a Load Configuration File dialog box that you use to load an existing configuration into the Test Manager. The harness does not open the Configuration Editor when you load an existing, complete configuration interview. See Loading a Configuration for detailed information.
Load Recent Configuration	Displays a list of recently opened configuration. You can choose a configuration from the list to use as the current configuration.
New Template	Opens the Template Editor and loads an empty template. The harness uses the Template Editor to create a template containing known test environment and standard values required to run a test suite. See Creating a Template for detailed information about templates.

TABLE 12 Configure Menu

Load Template	Opens a Load Template dialog box that you use to load an existing template into the Test Manager. See Loading a Template for detailed information.
Load Recent Template	Displays a list of templates that have been opened. You can choose a template from the list to use as the template for creating a configuration.
Update Template	Enabled only when template propagation is enabled and the template on which current configuration is based has changed. Displays a dialog box that enables you to import changes from the template into your configuration.

Run Tests Menu

The Run Tests menu is used to start, stop, and monitor a test run. This menu can be customized to include additional actions, so you may see additional options. A custom menu is developed as part of a test suite, so it is visible only when the test suite is in use.

The following table describes the default items in the Run Tests menu.

TABLE 13 Run Tests Menu

Menu Item	Description
 Start	The harness enables the Start menu item when it is not running tests. Choose the Start menu item to start a test run. Only one test run at a time can be active in the Test Manager. See Starting a Test Run for detailed information about starting a test run.
 Stop	The harness enables the Stop menu item when it is running tests. Choose the Stop menu item to end a test run after the current test is completed. See Stopping a Test Run for detailed information about stopping a test run.
Monitor Progress	When the harness is running tests, you can use the Progress Monitor to display the progress of the test run and current resource information about the test system. Choose the Monitor Progress menu item to open the Progress Monitor. See Using the Progress Monitor for detailed information about using the Progress Monitor.

Report Menu

The Report menu contains menu items that create and view reports about test run information. The following table describes the items in the Report menu.

TABLE 14 Report Menu

Menu Item	Description
Create Report	Opens the Create a New Report dialog box for you to generate reports of test results. See Creating Reports for detailed information.
Open Report	Opens the Report dialog box used to specify a report. See Displaying Reports for detailed information.
<i>Report History</i>	Displays a list of available reports. Choose a report from the list to open a new instance of it in the Report browser. See Displaying Reports for detailed information about the Report browser.

View Menu

The View menu contains menu items that display information about a test run. The following table describes the items in the View menu.

TABLE 15 View Menu

Menu Item	Description
Configuration > Show Checklist (Optional)	Enabled by the harness when your test suite supports the configuration checklist. Displays a checklist of tasks to be performed before running tests. See Displaying the Configuration Checklist for detailed information.
Configuration > Show Exclude List (Optional)	Opens an Exclude List dialog box that contains the exclude list used to run the test suite. You can use the Exclude List dialog box to review but not edit the contents of the exclude list. If you use multiple exclude lists, the Exclude List dialog box displays the merged set of exclude lists. You must use the configuration editor window to add or remove exclude lists. See Using Exclude Lists for detailed information. See Viewing Exclude List Contents for detailed information about viewing the contents of the exclude list.

TABLE 15 View Menu

Configuration > Show Test Environment	Opens a Test Environment browser that displays the configuration values used when running the test suite. You can browse but not change values in the Test Environment browser. You must use the configuration editor to change the values. See Editing a Configuration for detailed information. See Viewing Configuration Values for detailed information about viewing the contents of the test environment.
Configuration > Show Question Log	Displays a log of the current configuration interview questions and answers. See Displaying the Question Log for detailed information.
Filters	Displays the available view filters, the active filter, and enables you to modify the custom view filter. See Using View Filters for detailed description.
Properties	Click the Properties menu item to display the Test Manager Properties dialog box containing the current settings of the Test Manager. See Viewing Test Manager Properties for detailed information about using the Test Manager Properties dialog box.
Logs	Is enabled if the harness detects any log output, otherwise it is disabled. Click the Logs menu item to display logged output generated by the harness for the test suite.
Test Suite Errors	Enables the Test Suite Errors menu item when it detects that the test suite (not the tests in the test suite) contains errors. Click the Test Suite Errors menu item to display a dialog box identifying the errors detected in the test suite. See Viewing Test Suite Errors for detailed information.
Toolbars	Is enabled if more than one toolbar is available to the user, otherwise it is disabled.

Tool Bar

The tool bar contains the following fields and buttons used to perform routine tasks that are also available as menu items from the menu bar:

- **View Filter: Status of** - Filters the test status (folder colors and counters) displayed in the Test Manager.

View filters do not determine the tests that are run. You must use the configuration editor to change the tests that are run. See [Using View Filters](#) for detailed information about each filter.

- **Edit Filter** - Enabled only when Custom is selected in the view filter list.

See [Using View Filters](#) for detailed information about creating a custom view filter.

-  - Opens the Configuration Editor in Question Mode.

See [Question Mode](#) for a detailed description of this mode.

-  - Opens the Configuration Editor in Quick Set Mode.

See [Quick Set Mode](#) for a detailed description of the mode.

-  - Starts a test run.

See [Starting a Test Run](#) for a detailed description.

-  - Stops a test run.


See [Stopping a Test Run](#) for a detailed description.

-  - Displays User Guide information about the Test Manager.

Progress Monitor

The Progress Monitor is a dialog box that only displays information about the current configuration when the harness is running tests. The information displayed is equivalent to the Last Test Run view filter set in the Test Manager. Changing view filters in the Test Manager does not change the information displayed by the Progress Monitor.

Choose Run Tests > Monitor Progress from the Test Manager menu bar or click the  icon at the bottom of the Test Manager to open the Progress Monitor.



The following areas in the Progress Monitor display information about the test run:

- [Progress](#)
- [Tests in Progress](#)
- [Memory](#)
- [Time](#)

Progress

The following table describes the information displayed in the Progress area.

TABLE 16 Progress Area Contents

Name	Description
Passed	Displays the number of tests in the test suite that were run and had passing results.
Failed	Displays the number of tests in the test suite that were run and had failing results.
Errors	Displays the number of tests in the test suite that could not be run.
Not Run	Displays the number of tests in the test suite have not yet been run.
Test Results	A colored progress bar representing the results of the tests in the test suite. As the harness runs tests, the test results are displayed as colored segments in the progress bar. The colors used in the progress bar represent the current status of the test results. The colors below are the harness default settings. The harness supports using colors other than the default settings. See Specifying Status Colors in the <i>JavaTest Harness User's Guide: Command-Line Interface</i> . The progress bar is the same as that displayed in the test progress display at the bottom of the Test Manager.

The following table describes the colors used in the progress bar. The colors are displayed from left to right in the order in which they are presented in the table.

TABLE 17 Order of Colors Displayed in the Progress Bar

Color	Status	Description
Green	Passed	Tests in the test run having passing results when they were executed.

TABLE 17 Order of Colors Displayed in the Progress Bar

Red	Failed	Tests in the test run having failed results when they were executed.
Blue	Error	Tests in the test run that the harness could not execute. Errors usually occur because the test environment is not properly configured.
White	Not yet run	Tests in the test run that the harness has not yet executed. Tests excluded from the test run are not included.

You can display the progress bar in the Test Manager by clicking the button and choosing Run Progress Meter from the selectable list. See [Using the Progress Meter](#) for detailed description.

Tests in Progress

The Tests in Progress text box displays either the names of the tests that the harness is currently running or the set of tests distributed for execution. It is empty when the harness is not running tests. Concurrency settings and agents in use determine the number of items displayed in the text box. See your test suite documentation for additional information.

Clicking on this list displays the appropriate test view in the Test Manager.

Memory

The Memory area contains two text fields and a bar graph. The following table describes the contents of the Memory area in the Progress Monitor.

TABLE 18 Memory Area Contents

Name	Description
Used:	The memory used to run the test.
Total:	The total memory available for use by the virtual machine.

Time

The Time area contains two fields that are continuously updated throughout a test run. The following table describes the contents of the Time area in the Progress Monitor.

TABLE 19 Time Area Contents

Name	Description
Elapsed:	The time elapsed since the test run was started.
Remaining:	The estimated time required to run the remaining tests.

Tests that timeout or have execution times significantly longer than the other tests being run can cause the harness to display inaccurate times.

Progress Indicator

The progress indicator located at the bottom of the Information Area displays the elapsed time of the previous test run when tests are not running. When tests are running, it automatically changes to the progress bar of the current test run. At the completion of the test run, the indicator changes to display the elapsed time.

You can use the  button at any time to select and display either the elapsed time or the progress bar.

Elapsed Time

When a test run starts, the elapsed time display resets to 00.00.00. At the end of the test run, the total elapsed time for the test run is displayed.

Progress Bar


The harness displays a progress bar and a percentage complete value. As the harness completes a test, it updates the progress bar and the percentage complete value.

Information Area

The Test Manager uses the information area to display information about the item selected in the test tree. The Test Manager uses two views, folder view and test view, to display the information.

Folder View

When you click a folder icon in the test tree, the Test Manager displays a Summary tab, a Documentation tab, five status tabs, and a status field containing information from the work directory about a folder and its descendants.




The folder view contains filtered summary and status information about the tests in a test folder. The Test Manager also displays a status message at the bottom of the area about the selected view. The messages can indicate that tests in the folder are loading or they can provide detailed status information about a selected test.

During a test run, you can use the folder view to monitor the status of a folder and its tests. You can also use the folder view during troubleshooting to quickly locate and open individual tests that had errors or failed during the test run. When a status pane is empty, the Test Manager disables its tab. This information is displayed in the Summary tabbed pane as values and as a pie chart. The folder view and test tree use the same view filter when displaying information.

See [Displaying Folder Information](#) for detailed information about this view.

Test View

When you click a test icon in the test tree or double click its name in the Folder view, the Test Manager displays tabbed panes that contain detailed information about the selected test.



See [Displaying Test Information](#) for detailed information about this view.

Test Tree

The test tree is a multifunction panel that performs the following functions:

- Displays the current status and state of tests in the test suite
- Enables users to choose any combination of tests and folders in the test suite for a test run
- Enables users to refresh or to clear specific test results

The test tree supports keyboard navigation. See [Keyboard access](#) for a description of how the keyboard can be used to navigate the test tree pane.

Displaying Test Status and State

The test tree uses folder icons, test icons, and two independent types of filtering (run filtering and view filtering) to simultaneously display the progress of a test run and the current test results in the work directory.

The test tree indicates the progress of a test run by displaying an arrow to the left of each folder and test icon as it is loaded and run. See [Monitoring With a Test Tree](#) for detailed information about using the test tree to monitor a test run.

Based on the Test Manager view filter, the test tree updates the folder and test result icons to indicate the current test results in the work directory.

Example:

When you choose the Current Configuration view filter, the test tree only displays the results for the tests specified in your current configuration. If you choose the All Tests view filter, the test tree immediately redisplays all test results from the work directory regardless of the settings in your current configuration. To display filtered summary information about the test results in the work directory, click the test suite icon in the test tree.

See [View Filters](#) for a detailed description of how to specify which test results from the work directory are displayed in the test tree.

When you click a folder icon in the test tree, the harness displays its folder view in the Test Manager information area. The Test Manager uses the view filter to filter results displayed in the folder view. See [Displaying Folder Information](#) for additional information.

When you click a test icon in the test tree, the harness displays its test view in the Test Manager information area. Unlike the folder view, the Test Manager does not filter results in the test view. See [Test View](#) for additional information.

Run, Refresh, or Clear Results

You can select any combination of tests and test folders and right click in the test tree to open a pop-up menu for performing the following actions:

- Execute highlighted folders and tests by performing a quick pick execution.
- Refresh the list of folders and tests without restarting the harness by performing an on-demand refresh scan for new folders, new tests and updated test descriptions.

- Clear Results by performing an on-demand clearing of the contents of the highlighted folder, test, or entire work directory.

If a single test or folder is highlighted in the test tree, the Test Manager displays the appropriate Test View or Folder View. However, when multiple tests and folders are highlighted in the test tree, the harness displays a Multiple Tree Nodes Selected pane that lists the highlighted tests and folders. Highlight multiple tests and folders in the test tree by using standard keystrokes (such as Shift and Control) and clicking the test and folder icons in the test tree.

The selection list in the Multiple Tree Nodes Selected pane displays the full path of each node highlighted in the test tree. Click a test or folder in the test tree a second time to remove the highlighting and to remove it from the selection list. The GUI displays the updated Multiple Tree Nodes Selected pane.

Folders and tests do not have to be highlighted in the test tree for you to use the pop-up menu. See [Test Tree Pop-up Menu](#) for detailed information about using the pop-up menu.

Folder Icons

The test tree uses colored icons to indicate both run status and result status. The colors of the icons shown below are the default settings. The harness enables you to use colors other than the default settings. See Specifying Status Colors in the *Command-Line Interface User's Guide*.

Folder Run Status

When activity occurs in a folder, such as loading or running tests, the Test Manager displays an arrow to the left of the folder icon. The standard values of the current configuration, not the view filter, determine the run status displayed by the test tree.

Folder Result Status

The folder icon indicates the current test results in the work directory and does not change until its tests are completed. After the harness completes running the tests in a folder, it displays the appropriate result status icon.

The folder icon displayed in the test tree is determined by the result of all its tests (see [Test Icons](#)) and the current view filter (see [View Filters](#)). The folder icons displayed in the test tree indicate the highest priority result of any test hierarchically beneath it. The following table describes the folder icons in order of priority.

Note – Users can change the color of the folder icons displayed in the following table. However, the symbols displayed in the icons do not change.

TABLE 20 Folder Icon Descriptions and Priority Order

Icon	Result	Description
	Error	A blue folder containing an exclamation symbol (!) indicates that it and/or one or more of its child folders contains tests with a result of Error. Note that this folder <i>might</i> also contain tests and folders that are Failed, Not Run, Passed, and Filtered out.
	Failed	A red folder containing a x symbol indicates that it and/or one or more of its child folders contains tests with a result of Failed. Note that this folder <i>might</i> also contain tests and folders that are Not Run, Passed, and Filtered out.
	Not Run	A white folder containing a - symbol indicates that it and/or one or more of its child folders contains tests with a result of Not Run. Note that this folder <i>might</i> also contain tests and folders that are Passed and Filtered out.
	Passed	A green folder containing a ✓ symbol indicates that it and all of its children have a result of Passed. Note that this folder <i>might</i> also contain tests and folders that are Filtered out.
	Filtered Out	A gray folder containing no symbols indicates that it and all of its children are filtered out.

Test Icons

The test tree uses colored icons to indicate both run status and result status. The colors of the icons shown below are the default settings. The harness enables you to use colors other than the default settings. See Specifying Status Colors in the *Command-Line Interface User's Guide*.

Test Run Status

The Test Manager displays an arrow to the left of the test icon when running a test. The standard values of the current configuration, not the view filter, determine the run status displayed by the test tree.

Test Result Status

The test icon indicates the last known test result and does not change until the test is completed. After the harness completes the test, it displays the appropriate result status icon.

The test result icons displayed in the test tree are determined by the results in the work directory and by the view filter set in the Test Manager. See [View Filters](#) for a description of how to specify the test results displayed in the test tree. The following table describes the test icons used to indicate the result of each test.


Note – Users can change the color of the test icons displayed in the following table. However, the symbols displayed in the icons do not change.

TABLE 21 Test Icons

Icon	Result	Description
	Error	A blue test containing an exclamation symbol (!) indicates that the test is not filtered out and that harness could not execute it. These errors usually occur because the test environment is not properly configured.
	Failed	A red test containing a 'x' symbol indicates that the test is not filtered out and had a Failed result the last time it was executed.
	Not Run	A white test containing a '-' symbol indicates that the test is not filtered out but has not yet been executed.
	Passed	A green test containing a checkmark symbol indicates that the test is not filtered out and had a Passed result the last time it was executed.
	Filtered Out	A gray test containing no symbols indicates that the test is currently not selected to be run.

Test Tree Pop-Up Menu

The test tree provides a pop-up menu. Displaying the pop-up menu for a folder or test is a platform-specific operation (such as right clicking the folder or test icon in the test tree). You can also press Shift-F10 to display the pop-up menu for the test with focus.



The pop-up menu contains the following menu items:

- **Execute these tests** - See [Quick Pick Test Execution](#) for a detailed description.
- **Refresh** - See [Refresh Test Suite Contents](#) for a detailed description.
- **Clear Results** - See [Clear Previous Test Results](#) for a detailed description.

The harness does not allow you to perform operations using the pop-up menu when it is running tests. The harness displays an error dialog box if you attempt to perform an operation using the pop-up menu when tests are running.

See [Keyboard access](#) for a description of how you can use the keyboard to open and navigate the pop-up menu.

Quick Pick Test Execution

You can use the Execute these tests menu item to run the tests and folders highlighted in the test tree, subject to filters such as keywords.

The harness does not automatically perform a refresh operation before running the tests. If changes are made to a test suite, you must perform a refresh before running tests. See [Refresh Test Suite Contents](#) for a description of the refresh operation.

▼ Quick Pick Test Execution of Specific Folders or Tests

1. Select one or more folders and tests in the test tree.
 - You must left click to select nodes. When more than one folder or test is highlighted in the test tree, the Test Manager displays a list of the selected tests and folders in the information area.
 - Selecting a test executes only that test.
 - Selecting a folder executes all tests currently known to the Test Manager in and below that folder.
2. Right click in the test tree pane to open the pop-up menu.

Opening the pop-up menu is a platform-specific operation (such as right clicking in the test tree pane). A modifier key or operation which doesn't utilize the clicking at all may be necessary depending on your platform details.

3. Choose Execute these tests from the test tree pop-up menu.
 - If the Test Manager contains a completed configuration, the harness displays a message to confirm the execute operation.
 - If the Test Manager does not contain a completed configuration, the harness displays a message asking you to complete the configuration or cancel the test run.

Note – The harness combines the [current configuration](#) and the nodes selected in the test tree to determine which tests will be executed. In the [Test Manager Preferences](#), the option Execution from tree popup includes configuration Tests to Run how the harness uses the Tests to Run value in the configuration, as described below:

Box is unchecked (default). The harness ignores the tests specified in the [current configuration](#)'s Tests to Run question. It runs the tests selected in the test tree, subject to configuration Test Selection filters, such as keywords. This option is compatible with the behavior of test harnesses older than version 4.2.1.

Box is checked. The harness compares the tests you selected in the test tree and the tests specified in the configuration's Tests to Run question to find a set of common tests. The harness then applies the configuration's Test Selection filters (such as keywords) to the common test set, producing the set of eligible tests.

4. Tests will be executed. The above test selection process and exclusions from the criteria defined by the test suite or interview may eliminate all the eligible tests. If this happens you will see a message, and the test run is aborted.

Refresh Test Suite Contents

When developing tests, changes in a test suite are not automatically detected by the harness. The first time tests are run, the harness uses the test finder to read test descriptions. If the harness loads tests from an existing work directory, the test descriptions contained in those results are used by default.

The refresh operation enables test developers to load changes they might have made in a test suite without restarting the harness or reloading the test suite.

The harness does not require a work directory to perform a refresh of the test suite.

If you are viewing the test panel after refreshing a test or folder, update the test tree by choosing a different test or folder icon and repeating your test tree choice.

▼ Refresh Tests and Folders

1. Select one or more folders and tests in the test tree.
 - You must left click to select a node. When more than one folder or test is highlighted in the test tree, the Test Manager displays a list of the selected tests and folders in the information area.
 - Selecting a test chooses only that test.
 - Selecting a folder chooses all tests currently known to the Test Manager in and below that folder.
2. Right click in the test tree to open the pop-up menu.
Opening the pop-up menu is a platform-specific operation (such as right clicking in the test tree).
3. Choose Refresh from the pop-up menu.
4. For files, the harness checks the time stamp of the file containing the test description.
5. If the time stamp has changed, the harness compares the test descriptions.
6. If the properties of the test descriptions are different, the harness removes the test result from the work directory and the Test Manager and loads a test containing the new test description into the Test Manager and displays it in the Not Run state.
7. For folders, the harness checks the time stamps of the files in a folder and scans for new folders and tests. This operation may take place on any folder including the root folder.
8. If a time stamp has changed, the harness compares the test descriptions.

9. If the properties of the test descriptions are different, the harness removes the test result from the work directory and the Test Manager and loads the test containing the new test description into the Test Manager and displays it in the Not Run state.

Clear Previous Test Results

You can use the Clear Results menu item to remove existing test results for any combination of tests and folders.

To clear test results, you must have an open work directory.

▼ Clear a Test Result

1. Select one or more tests in the test tree.

You must left click to select a node. When more than one test is highlighted in the test tree, the Test Manager displays a list of the selected tests and folders in the information area.

2. Right click in the test tree to open the pop-up menu.

Opening the pop-up menu is a platform-specific operation (such as right clicking in the test tree).

3. Choose Clear Results from the test tree pop-up menu.

The harness opens a confirmation dialog box that displays a list of the selected items and performs the following actions when the user clicks the Yes button:

- Removes the .jtr file from the work directory for that test.
- Refreshes the test description for that test.
- Displays the test in the Not Run state.

▼ Clear Test Results in Folders

1. Select one or more folders in the test tree.

You must left click to select a node. When more than one folder is highlighted in the test tree, the Test Manager displays a list of the selected tests and folders in the information area.

2. Right click in the test tree pane to open the pop-up menu.

Opening the pop-up menu is a platform-specific operation (such as right clicking in the test tree).

3. Choose Clear Results from the test tree pop-up menu.

The harness displays a confirmation dialog box that displays a list of selected items and performs the following actions when the user clicks the Yes button:

- Removes all `.jtr` files from the work directory for all tests in and below that folder.
- Deletes all other files in and below the folder in the work directory.
- Deletes all other directories corresponding to the folders in and below the folder in the work directory.
- Displays the folder and its tests as Not Run.

The harness does not display an error message if it is unable to delete a folder or file from the work directory.

View Filters

The harness provides a special view filtering facility that enables you to filter the status (the colors and counters) of the folders and tests displayed in the Test Manager. View filters function independently from the run filtering set in the configuration editor window.

See [Editing a Configuration](#) for detailed information about specifying the tests that are run.

Note – You also use view filters when generating reports. See [Creating Reports](#) for a description of using view filters when generating reports.

The harness provides four Test Manager view filters:

- [Last Test Run](#)
- [Current Configuration](#)
- [Current Template](#)
- [All Tests](#) (default)
- [Custom](#)

An additional view filter, such as a Certification filter, can be added by the test suite. Refer to your test suite documentation for detailed descriptions of any additional filters displayed in the list of view filters.

To use a view filter, either choose View > Filters from the menu bar or choose a view filter from the tool bar. See [Custom View Filter](#) for a description of how to create a custom view filter.

If you checked the Save Desktop State on Exit option in the Preferences dialog box, the current view filter information is saved when you exit.

Current view filter information is **not** saved if you:

- unchecked the Save Desktop State on Exit option in the Preferences dialog box
- provided test suite or work directory information on the command line when starting the harness
- used the `-newDesktop` on the command line when starting the harness

[See Shutdown Options.](#)

Last Test Run View Filter

When you select the Last Test Run view filter, the Test Manager displays the current totals in the Summary pane and status icons in the test tree for all folders and tests included in the last test run (even if you have exited the harness since the last test run) or the states from the test run in progress if the harness is running tests. The information displayed in the Test Manager is associated with the work directory.

The following examples provide descriptions of the use of the Last Test Run view filter:

- **Example 1** - A test run had failed tests and you want to rerun only the failed tests. See [Specifying Prior Status](#) for a detailed description of setting the prior status value. The Test Tree and the Summary pane continue to show all tests in the last test run regardless of their status.

When you repeat the test run, the Test Manager clears the previous test results and only displays current status icons in the test tree and totals in the Summary pane for the tests and folders in the current test run.

- **Example 2** - A test run had failed tests and you want to use an Exclude List in the next run that excludes the failed tests from the test run. See [Using Exclude Lists](#) for a detailed description of specifying an exclude list. The Test Tree and the Summary pane do not change when the exclude list is added to the configuration.

When you repeat the test run, the Test Manager clears the previous test results and only displays current status icons in the test tree and totals in the Summary pane for the tests and folders in the current test run.

Current Configuration View Filter

When you select the Current Configuration view filter, the Test Manager only displays the status of the folders and tests currently selected by the current configuration.

To select the Current Configuration view filter, choose View > Filter > Current Configuration from the menu bar or choose the Current Configuration view filter from the tool bar.

The following examples provide descriptions of the use of the Current Configuration view filter:

- **Example 1** - You only want to run and view the results for tests in the api folder. See [Specifying Tests to Run](#) for detailed description of specifying the tests that are run.

Either choose View > Filter > Current Configuration from the menu bar or choose the Current Configuration view filter from the tool bar.



The Test Manager displays gray folder and test icons for all folders and tests except those under api. The Test Manager changes the Summary totals to indicate that these tests are filtered out.

The current result icons are only displayed in the test tree for those folder and test icons under api and the Summary pane is updated to display their totals. When you run the tests, the test tree and folder view only display the results for those folders and tests under api.

- **Example 2** - You only want to run and view results for failed tests. See [Specifying Prior Status](#) for a detailed description of setting the prior status value.

Either choose View > Filters > Current Configuration from the menu bar or choose the Current Configuration view filter from the tool bar.



Immediately the Test Manager displays gray folder and test icons for all folders and tests except those with Failed test results. The Test Manager updates the Summary totals to indicate that these tests are filtered out and changes the Passed, Error, and Not Run totals to indicate 0.

The Test Manager displays those folders and tests in the test tree with Failed test

results as red folder and test icons. The Test Manager updates the Summary information to indicate the number of tests that have Failed test results.

When you repeat the test run, as failed tests pass, the Test Manager updates their icons from red  folder and  test icons to gray  folder and  test icons (they no longer match the configuration criteria of the view filter). The Test Manager updates the totals in the Summary pane to match the results displayed in the test tree.

Current Template View Filter

When you select the Current Template view filter, the Test Manager only displays the status of the folders and tests selected by the template on which the current configuration is based.

Select the Current Template view filter by either choosing View > Filter > Current Template from the menu bar or choosing the Current Template view filter from the tool bar.

All Tests View Filter

When you select the All Tests view filter, the Test Manager immediately displays current totals in the Summary pane and status icons in the test tree for all folders and tests, regardless of the values set in the configuration. This is an unfiltered view of the complete work directory contents.

The harness only overwrites the previous results for tests when they are rerun. The All Tests filter displays the last run status for all tests in the work directory, including the tests that were excluded from the current test run.

If you are using the All Tests view filter and begin a test run, the harness displays an advisory dialog box. Using the All Test view filter will display the results of all tests in a test suite regardless of whether or not they are included in the test run.

You can choose to disable the dialog box by setting preferences, by choosing a different view filter, or by using the check box in the dialog to stop the dialog from being displayed in the future.

The following examples provide descriptions of the use of the All Tests view filter.

- **Example 1** - A test run had failed tests and you want to rerun only the failed tests. See [Specifying Prior Status](#) for a detailed description of setting the prior status value. The Test Tree and the Summary pane do not change.

When you use the All Tests view filter, the Test Manager displays all totals in the Summary pane and status icons in the test tree regardless of the values set in the current configuration.

- **Example 2** - A test run had failed tests and you want to use an Exclude List in the next run that excludes the failed tests from the test run. See [Using Exclude Lists](#) for a detailed description of specifying an exclude list. The Test Tree and the Summary pane do not change.


When you repeat the test run, the Test Manager displays current status icons in the test tree and totals in the Summary pane for every test in the work directory, including results for any tests excluded from the current test run.

Custom View Filter

If you want to monitor a specific set of test results in the Test Manager, you can create a custom view filter.

The custom view filter is unique to the test suite. When the harness opens the test suite in the Test Manager, it restores the custom filter, including any name that you assign it.

You can also use the custom filter to generate reports. See [Creating Reports](#) for a description of using the Custom filter when generating reports.



▼ Creating a Custom View Filter

1. Choose **View > Filter > Configure Filters** from the menu bar to open the Filter Editor. You can also choose **Custom** and then **Edit Filter** in the tool bar.
2. Choose **Custom** in the Available Filters panel. You can provide a name for the filter in the Custom Label field. The name is applied to the filter and restored each time the test suite is opened.
3. Use the tabbed panes to set the following view filter properties:
 - [Specify Tests to View](#)
 - [Use the Exclude List as a View Filter](#)
 - [Use Keywords as a View Filter](#)
 - [Use Prior Status as a View Filter](#)

- [Use Special Settings as a View Filter](#)

4. Click one of the following buttons:

- **Apply** - Saves but does not dismiss the dialog box. Updates the GUI if the filter is selected.
- **Reset** - Discards all changes and restores the last saved Custom filter.
- **Cancel** - Closes the dialog box without saving any changes.
- **OK** - Saves the current changes, updates the Custom filter, and closes the dialog box.
- **Help** - Displays online help for the Filter Editor.

Using Test Suite Areas, Keywords, Prior Status, Exclude Lists, and Special settings in the view filter does not stop the harness from running these tests. To filter the tests that are run, you must change the values in the configuration. See [Editing a Configuration](#) for a detailed description.

Specify Tests to View

Click the Test Suite Areas tab and use the tree to choose the results of test folders or individual tests that you want displayed in the Test Tree. The harness walks the test tree starting with the sub-branches and tests you specify and displays the results of all tests that it finds.

Use Keywords as a View Filter

If your test suite provides keywords, you can use the Keywords pane to restrict the set of test results displayed in the test tree and in the Summary pane.

To specify the keywords:

1. Click Match.

The harness enables the Expression button.

2. Click Expression to display a list of expressions that can be constructed.

3. From the list, choose the type of expression that you are building.

4. In the text field, enter the keywords and operators used in the expression.

The following table provides descriptions and examples of keyword expressions that can be constructed.

TABLE 22 Keyword Expressions

Expression	Description
Any Of	<p>Displays all tests in the test suite having <i>any</i> of the keywords entered in the text field.</p> <p>Example:</p> <p>A test suite uses the keyword <code>interactive</code> to identify tests that require human interaction, and <code>color</code> to identify tests that require a color display.</p> <p>To display only the results for tests containing the <code>interactive</code> keyword, choose <code>Any Of</code> and then use the <code>interactive</code> keyword.</p>
All Of	<p>Displays results for all tests in the test suite having <i>all</i> of the keywords entered in the text field.</p> <p>Example:</p> <p>To display results for only the tests containing both the <code>interactive</code> and <code>color</code> keywords, choose <code>All Of</code> and then use the <code>interactive</code> and <code>color</code> keywords.</p>
Expression	<p>Displays results for all tests in the test suite having the <i>expression</i> entered in the text field.</p> <p>Construct a Boolean expression in the text field. Keywords stand as Boolean predicates that are true if, and only if, the keyword is present in the test being considered. A test is accepted if the overall value of the expression is true. All other tests are rejected by the restriction.</p> <p>Example:</p> <p>A test suite uses the keyword <code>interactive</code> to identify tests that require human interaction, and <code>color</code> to identify tests that require a color display.</p> <p>To display results for only the tests with the <code>color</code> keyword that do not also contain the <code>interactive</code> keyword, choose <code>Expression</code> and then use the <code>color</code> keyword, the <code>!</code> operator, and the <code>interactive</code> keyword.</p>

Use Prior Status as a View Filter

Click the Prior Status tab and choose the test results from the previous test run that you want displayed in the Test Tree.

TABLE 23 Using Prior Status as a Filter

Prior Status Filter	Action
Passed	Displays tests with passed results the last time the test was executed.
Failed	Displays tests with failed results the last time the test was executed.
Error	Displays tests that the harness could not execute the last time it was included in a test run.
Not Run	Displays tests without results in the current work directory.

Prior status is evaluated on a test-by-test basis using information stored in the result files (.jtr) that are written in the work directory. Unless overridden by a test suite, a result file is written in the work directory for every test that is executed. When you change work directories between test runs, the result files in the previous work directory are no longer used and, if the new work directory is empty, the harness behaves as though the test suite was not run.

Use the Exclude List as a View Filter

To use the exclude list specified in the configuration interview as a filter, click the Exclude Lists tab and the Use settings in interview check box. The Exclude Lists pane displays the name of the exclude list file used by the current configuration.

Any test in the exclude list is filtered out and displayed as a  icon in the test tree.

Use Special Settings as a Filter

If the test suite architect provides a default filter for the test suite, click the Special tab and the Enable test suite filter check box to select this filter.

You must select this setting to correctly simulate the Current Configuration settings.

Use a Custom View Filter

To use a custom filter, you must choose it from the list of view filters below the test tree or from the View > Filters menu. The Test Manager updates the status of the folders and tests in the test tree that match the filter settings of the custom filter.


Work Directory Status Line

The work directory status line displays the current work directory or file name (for the full path, choose View > Properties), the configuration associated with the work directory, and the name of the template (if any) used to create the configuration.



Test Manager Status Line

The status message line is a resizable text area at the bottom of the Test Manager that displays information about current Test Manager activity, such as the state of a test run and the name of the test being run.



Note – If more than one test is running at a time, the Test Manager only displays the name of the last test started in the status message.


Configuration Editor

The Configuration Editor provides you with the following edit modes:

- Question Mode

■ Quick Set Mode


In Question Mode, the Configuration Editor displays all of the questions and values in a configuration interview.



You can choose **Configure > Edit Configuration** from the menu bar. You can also open the Configuration Editor in Question edit mode by clicking the button in the tool bar. After the Configuration Editor opens, you can use the View menu at any time to change edit modes without losing your changes.

See [Question Mode](#) for detailed information about this editing mode.

In Quick Set Mode, the Configuration Editor displays (in tab pane form) the runtime questions from a configuration interview. These are the values that specify which tests are run and how they are run. These values frequently change from test run to test run.




You can open the Configuration Editor in Quick Set edit mode by choosing **Configure > Edit Quick Set** from the menu bar. You can also open the Configuration Editor in Quick Set edit mode by clicking the button in the tool bar.

See [Quick Set Mode](#) for detailed information about this editing mode.

Question Mode

The Question Mode displays the complete configuration, allowing you to create a new configuration, change the values in a configuration, or search for character and value strings in a configuration.



1. [File Menu](#)
2. [Bookmarks Menu](#)
3. [Search Menu](#)
4. [View Menu](#)
5. [Help Menu](#)
6. [More Info Pane](#) (can be hidden)
7. [Question Pane](#)
8. [Index Pane](#)

Menus

In Question Mode, the Configuration Editor contains menus used to load, create, display, and change a configuration.

File Menu

The File menu contains items to open, save, and restore configuration files. The following table describes the items in the Configuration Editor File menu.

TABLE 24 Configuration Editor File Menu

Menu Item	Description
Save	Saves the current configuration. Choose File > Save at any time to save your answers and position in the configuration file. If the configuration is new, the editor opens the file chooser for you to use in naming and saving the current configuration. If you do not provide the .jti extension when you name the file, the editor adds the extension when it saves the file.
Save As	Opens a dialog box that you can use to save a configuration with a new name. The Configuration Editor makes the saved configuration the current configuration. If you do not provide the .jti extension when you name the configuration file, the editor adds the extension when it saves the file.
Revert	Discards any changes to the current configuration and restores the last saved version of configuration file.
New Configuration	Clears the current configuration and starts a new configuration. See Creating a Configuration for a detailed description.
Load Configuration	Opens an existing configuration file and makes it the current configuration. See Loading a Configuration for a detailed description.
Load Recent Configuration	Displays a list of configuration files that have been opened in the Configuration Editor window. Choose a configuration file from the list to open it in the Configuration Editor window.
New Template	Provides the option to save or clear the current template before starting a new template. See Creating a Template for a detailed description.
Load Template	Opens an existing template. See Loading a Template for a detailed description.
Load Recent Template	Displays a list of templates that have been opened in the Template Editor. Choose a template from the list to open it in the Template Editor.
Close	Closes the Configuration Editor window.

Bookmarks Menu

The Bookmarks menu contains items to use bookmarks in the configuration. The following table describes the items in the Bookmarks menu.

TABLE 25 Configuration Editor Bookmarks Menu

Menu Item	Description
Enable Bookmarks	Enables and disables bookmarking in the configuration.
Show Only Bookmarked Questions	Display only the marked questions or all questions.
Mark Current Question	Clears the bookmark from a selected question in the Configuration Editor window.
Unmark Current Question	Bookmarks the selected question in the Configuration Editor window. Enabled only if the selected question is not bookmarked.
Clear Answer For Current Question	Clears the answer for a selected question in the Configuration Editor window. Enabled only if the selected question is bookmarked.
Open Group	Expands a selected set of questions in the Configuration Editor window.
Clear Answers to Bookmarked Questions	Clear the values in all marked questions.
Remove Bookmarks	Remove all bookmarks from the configuration.

Using bookmarked questions enables the user to display only those configuration questions that must be answered. See [Using Bookmarks in Configurations](#) for a description of how the Bookmarks menu can be used to specify the questions that the Configuration Editor window displays.

Search Menu

Use the Search menu items to find the occurrence in a configuration of a specific character or value string. When troubleshooting a test run, you can use the Search menu to quickly locate an answer that needs to be changed. The following table describes the items in the Search menu.

TABLE 26 Configuration Editor Search Menu

Menu Item	Description
Find	Opens a dialog box used to search the configuration for a specific character or value string.
Find Next	Searches the configuration for the next occurrence of a specific character or value string.

See [Searching a Configuration](#) for a detailed description of how to search for character and value strings in a configuration.

View Menu

Use the View menu to display the Configuration Editor window in Question Mode or in Quick Set Mode, to hide or display the More Info pane, and to display question tag field at the bottom of each question panel. The following table describes the items in the View menu.

TABLE 27 Contents of the View Menu

Menu Item	Description
Question Mode	Displays the Configuration Editor window in Question Mode.
Quick Set Mode	Displays the Configuration Editor window in Quick Set Mode.
More Info	Displays and hides the More Info pane in the Configuration Editor window.
Question Tag	Displays and hides the Question Tag field in the Configuration Editor Question Pane.
Refresh	Updates the values and questions displayed in the Configuration Editor window.

Help Menu

Use the Help menu to display the online help for the Configuration Editor window and both editor modes. The following table describes the items in the Help menu.

TABLE 28 Configuration Editor Help Menu

Menu Item	Description
Configuration Editor	Displays online help for the Configuration Editor window.
Template Editor	Displays online help for the Template Editor window.
Question Mode	Displays online help for the Question Mode.
Quick Set Mode	Displays online help for the Quick Set Mode.

Index Pane

When completing a configuration, the index pane lists the titles of the questions you have answered, are currently answering, or that the editor determines might need to be answered. The current question is highlighted.

In completed configurations, the questions that are displayed in the index can be controlled by setting bookmarks in the configuration. See [Bookmarks Menu](#).

Note – The title is also displayed at the top of the question pane when you are answering a question.

Click on any question in the index list to make it the current question. Clicking on a question does not cause the list to change. If you change an answer that alters the configuration options, the Configuration Editor window updates the questions in the list to reflect the change in options. If a previously answered question is no longer displayed in the index list, the Configuration Editor saves its answer until you either save the configuration or change its value.

You can also use the buttons at the bottom of the Question pane to navigate through the configuration file. See [Question Pane](#) for a description of the navigation buttons.

Question Pane

The Configuration Editor window displays configuration questions in the main text area of the editor. You answer the questions using controls such as text boxes, radio buttons, or combo boxes located beneath the question. After you answer each

question, click  at the bottom of the panel to proceed to the next question.

The buttons at the bottom of the Question pane control the following functions:

- **Back** - Returns to the previous question.
- **Last** - Advances as far as possible through the configuration.
- **Next** - Proceeds to the next question.
- **Done** - Saves your answers as a configuration and closes the Configuration Editor window.

See [Creating a Configuration](#) for information about using the Question pane to create a configuration.

See [Editing a Configuration](#) for information about using the Question pane to edit the current configuration.

More Info Pane

To open and close the More Info pane, choose View > More Info from the menu bar.


The More Info pane provides additional information about each question, including the following:

- Background information about the question
- Information about choosing an answer
- Examples of answers

See [Keyboard access](#) for a description of how the keyboard can be used to navigate the More Info pane.

Quick Set Mode

Quick Set Mode uses tabbed panes to display the values of a configuration that the harness uses to determine which tests are run and how they are run. Because they might change from test run to test run, the Quick Set Mode enables the user to quickly locate and edit these values.



Quick Set Mode displays only the values that apply to your test suite. Tabs containing values that do not apply to your test suite are not displayed in Quick Set Mode. Depending on your test suite, Quick Set Mode can display four, five, or six tabbed panes and a menu bar.

- [Tests](#)
- [Exclude List](#)
- [Keywords \(Optional\)](#)
- [Prior Status](#)
- [Execution](#)


To use Quick Set Mode, a configuration must be loaded in the Configuration Editor. See [Editing Quick Set Values](#) for a description of how to change the Quick Set values of a configuration.

Template Editor

You can open the Template Editor by choosing **Configure > New Template**, **Configure > Load Template**, or **Configure > Load Recent Template** in the Test Manager menu bar. Like the Configuration Editor, the Template Editor provides users with the following two modes of displaying and working with the questions and values in a template.

- Question Mode
- Quick Set Mode

The harness always opens the Template Editor in Question Mode.




In Question Mode, the Template Editor displays all of the questions in the interview and enables the Bookmarks feature. You can use the Bookmarks feature to only display those questions in a template that a user must answer.

You can use the View menu at any time to change from one mode to the next. Because there is only one template file loaded in the Template Editor at a time, when you change viewing modes during an editing session, any changes that you have made in one viewing mode are automatically reflected in the other viewing mode.

See [Question Mode](#) for detailed information about using this mode to create or edit templates.

In Quick Set Mode, the Template Editor filters out the test suite specific questions and displays the remaining questions in logical groupings of the values. The Quick Set Mode displays them in tab form for easy user navigation and access. These values are the same as those values displayed in Question Mode. Only the form of their presentation to the user is different.




In Quick Set Mode, the Bookmarks and Search functions are not enabled.

See [Quick Set Mode](#) for additional information about using this mode to edit templates.

Question Mode

The Question Mode displays all questions in a test suite interview, allowing you to create a new template, edit an existing template, or search a template for specific characters or text.



1. [File Menu](#)
2. [Bookmarks Menu](#)
3. [Search Menu](#)
4. [View Menu](#)
5. [Help Menu](#)
6. [More Info Pane](#) (can be hidden)
7. [Question Pane](#)
8. [Index Pane](#)

Menus

In Question Mode, the Template Editor contains menus used to load, view, search, create, and edit a template.

File Menu

The File menu contains items to open, save, and restore template files. The following table describes the items in the File menu.

TABLE 29 Template Editor File Menu

Menu Item	Description
Save	Saves the current template. Choose File > Save at any time to save your answers and position in the template. If the template is new, the editor opens the file chooser for you to name and save the current values. If you do not provide the .jtm extension when you name the file, the editor adds the extension when it saves the template.
Save As	Opens a dialog box that you can use to save a template with a new name or change the location of the template. If you do not provide the .jtm extension when you name the template, the editor adds the extension when it saves the file.
Revert	Discards any changes to the current template and restores the last saved version of the template.
New Configuration	Clears the current configuration and starts a new configuration. See Creating a Configuration for a detailed description.
Load Configuration	Opens an existing configuration file and makes it the current configuration. See Loading a Configuration for a detailed description.
Load Recent Configuration	Displays a list of configuration files that have been opened in the Configuration Editor window. Choose a configuration file from the list to open it in the Configuration Editor window.
New Template	Provides the option to save or clear the current template before starting a new template. See Creating a Template for a detailed description.
Load Template	Opens an existing template. See Loading a Template for a detailed description.
Load Recent Template	Displays a list of templates that have been opened in the Template Editor. Choose a template from the list to open it in the Template Editor.
Close	Closes the Template Editor.

Bookmarks Menu

The Bookmarks menu contains items used to manage bookmarks in the template. Using bookmarked questions enables the user to display only those template questions that must be answered. See [Setting Markers](#) for a description of how the Bookmarks menu can be used to specify the questions that the Template Editor displays.

The following table describes the items in the Bookmarks menu.

TABLE 30 Template Editor Bookmarks Menu

Menu Item	Description
Enable Bookmarks	Enables or disables bookmarking in the template. When bookmarking is disabled, the remaining bookmark menu items are grayed out.
Show Only Bookmarked Questions	Displays only the bookmarked questions.
Mark Current Question	Sets the bookmark for a question selected in the index pane.
Unmark Current Question	Clears the bookmark from a question selected in the index pane. Enabled only if the selected question is bookmarked.
Clear Answer For Current Question	Clears the answer for a selected question in the index pane. Enabled only if the selected question is bookmarked.
Open Group	Expands a selected set of questions in the index pane.
Clear Answers to Bookmarked Questions	Clears the values in all bookmarked questions.
Remove Bookmarks	Removes all bookmarks from the Template.

Search Menu

Use the Search menu items to find the occurrence in a Template of a specific character or value string. When troubleshooting a test run, you can use the Search menu to quickly locate an answer that needs to be changed. See [Searching the Template](#) for a detailed description of how to search for character and value strings in a Template.

The following table describes the items in the Search menu.

TABLE 31 Template Editor Search Menu

Menu Item	Description
Find	Opens a dialog box used to search the template for a specific character or value string.
Find Next	Searches the template for the next occurrence of a specific character or value string.

View Menu

Use the View menu to display the Template Editor in Question Mode or in Quick Set Mode, to hide or display the More Info pane, and to display question tag field at the bottom of each question panel. The following table describes the items in the View menu.

TABLE 32 Contents of the Search Menu

Menu Item	Description
Question Mode	Displays the Template Editor in Question Mode.
Quick Set Mode	Displays the Template Editor in Quick Set Mode.
More Info	Displays and hides the More Info pane in the Template Editor.
Question Tag	Displays and hides the Question Tag field in the Template Editor Question pane.
Refresh	Updates the values and questions displayed in the Template Editor.

Help Menu

Use the Help menu to display the online help for the Template Editor and both editor modes. The following table describes the items in the Help menu.

TABLE 33 Template Editor Help Menu

Menu Item	Description
Configuration Editor	Displays online help for the Configuration Editor.
Template Editor	Displays online help for the Template Editor.
Question Mode	Displays online documentation for the Question Mode.
Quick Set Mode	Displays online documentation for the Quick Set Mode.

Index Pane

When completing a template, the index pane lists the titles of the questions you have answered, are currently answering, and any questions that the editor can determine might need to be answered. The current question is highlighted and its title is displayed at the top of the question pane.

The number of questions displayed in the configuration interview is controlled by setting bookmarks in the template. See [Bookmarks Menu](#) for procedures used to reduce the number of questions displayed in the configuration interview.

Click on any question in the index list to make it the current question. Clicking on a question does not cause the list to change. If you change an answer that alters the Template options, the Template Editor updates the questions in the list to reflect the change in options. If a previously answered question is no longer displayed in the index list, the Template Editor saves its answer until you either save the Template or change its value.

You can also use the buttons at the bottom of the Question pane to navigate through the Template file. See [Question Pane](#) for a description of the navigation buttons.

Question Pane

The Template Editor displays template questions in the main text area of the editor. You answer the questions using controls such as text boxes, radio buttons, or combo boxes located beneath the question. After you answer each question, click



at the bottom of the panel to proceed to the next question.

The buttons at the bottom of the Question pane control the following functions:

- **Back** - Returns to the previous question.
- **Last** - Advances as far as possible through the template.
- **Next** - Proceeds to the next question.
- **Done** - Saves your answers as a template and closes the Template Editor.

See [Creating a Template](#) for information about using the Question pane to create a template.

See [Editing a Template](#) for information about using the Question pane to edit the current template.

More Info Pane

To open and close the More Info pane, choose View > More Info from the menu bar.


The More Info pane provides additional information about each question, including the following:

- Background information about the question
- Information about choosing an answer
- Examples of answers

See [Keyboard access](#) for a description of how the keyboard can be used to navigate the More Info pane.

Quick Set Mode

Quick Set Mode uses tabbed panes to display only the runtime values of a template.




Runtime values are used to choose the tests that are run and specify how tests are run. These values can change from test run to test run. Quick Set Mode displays only the runtime values that apply to your test suite. The tabs containing runtime values that do not apply to your test suite are not displayed in Quick Set Mode.

- [Tests](#)
- [Exclude List](#) (optional)
- [Keywords](#) (optional)
- [Prior Status](#)
- [Environment](#) (optional)
- [Execution](#) (optional)

Quick Set Mode is not enabled until a template is either loaded or started in the Template Editor. See [Editing a Template](#) for detailed information about editing a template.

Log Viewer

Use the Log Viewer to view the log contents during or after a test run. The test suite generates the logs that are displayed in the viewer. The following illustration is an example of the content that a test suite might generate. See your test suite documentation for detailed information about the log files that it generates.



1. Selection Action list
2. Logs and levels pane
3. Log Message pane
4. Close button
5. Open New Log Viewer button
6. Save...
7. Clear Log button
8. Find text field.
9. Live Scrolling check box
10. Word Wrap check box

Selection Action List

The Selection Action list consists of three sections of message selection actions (log levels) that a user might choose for displaying the message of a log. A log is a series of notifications concerning a component of the system. Log levels are descriptive criteria applied to each message within a log.

The first section of the list enables the user to either Select All log levels for display in the log viewer or to Unselect All. The second section of the list enables the user to select one or more general message log levels for display. In the example illustration, these messages are represented by the General Logger messages. The third section of the list enables the user to select one or more test suite log levels for display. In the example illustration, these message types are represented by the TSM Logger message types.

The choices in this list only change the current state of selections. These selections would not apply to the new log which is displayed after the user chooses Select All.

Logs and Levels Pane

The log viewer displays a list of log levels available from the test suite that has been selected for display. You can select one or more of the log levels in any combination. These log levels are also listed in the Selection Action list. As in the Selection Action list, the log levels are grouped into general types. See Selection Action List for a description of logs and log levels. See your test suite documentation for detailed information about the log messages that it generates.

Log Message Pane

The contents of the output log specified by the selections in the logs and levels pane are displayed as text. The test suite specifies the output log contents displayed in the viewer. See your test suite documentation for detailed information about the log file contents that it generates.

Close Button

The Close button closes the log viewer. If multiple log viewers are open during a test run to monitor specific sets of log messages, the Close button only closes the log viewer to which it is bound.

Open New Log Viewer Button

Use the Open New Log Viewer button to open an empty log viewer. During a test run, multiple log viewers can be opened and used to monitor specific sets of log messages.

Save Button

Click the Save button to save the contents of the Log Viewer as an XML file.

Clear Log Button

Click the Clear Log button to erase the contents displayed in the log viewer and usually stored on a disk. These contents are automatically loaded the next time that the work directory is opened.

Find Text Field

Use the Find Text field to search the contents of the log message pane for specific text strings.

Live Scrolling Check Box

Check to monitor for log output while the harness runs. Log entries can be generated at any time, not just while tests are running.


Word Wrap Check Box

Check the Work Wrap check box to cause the log viewer to wrap long line of content in the log message pane.

Test Results Auditor Tool

Use the Test Results Auditor tool (Audit tool) to generate and view an audit report of the test results in a work directory. The Audit tool verifies that all tests in a test suite ran correctly and identifies any audit categories in a test run with errors. To

launch the Audit tool, choose Tools > Test Results Auditor from the menu bar. The harness opens the tool window and an options dialog box. The options dialog box is used to specify the audited test suite, work directory, and configuration file.



The Test Results Auditor contains the following items:

1. [Audit Tool Menu Bar](#)
2. [Audit Settings](#)

3. [Audit Results](#)

See [Audit Test Results Options](#) for a detailed description of the options dialog box.

See [Auditing Test Results](#) for a detailed description of using the Audit tool to generate and view an audit report of the test results in a work directory.

Audit Tool Menu Bar

The Audit tool menu bar contains an Audit and a Help menu.

Use the Audit menu to set options used to generate an audit report. See [Audit Test Results Options](#) for a description of the Options dialog box.

Use the Help menu to display online help for the Test Results Auditor window.

See [Menus](#) for a description of the harness standard menus that are displayed on the menu bar.

Audit Settings

The following audit settings are displayed at the top of the window:

- **Test Suite** - Displays the name and location of the reference test suite.
- **Work Directory** - Displays the name and location of the audited work directory.
- **Configuration File** - Displays the name and location of the reference configuration interview.

Use the options dialog box to specify the values in these fields. See [Audit Test Results Options](#) for a detailed description of the options dialog box.

Audit Results

The harness displays the audit report in the following five tabbed panels:

- [Summary](#)
- [Bad Result File](#)
- [Bad Checksum](#)
- [Bad Test Description](#)
- [Bad Test Cases](#)

Summary

The following table describes the audit category state and details displayed in the Summary panel.

TABLE 34 Summary Panel Contents

Category	Description
Result Files	Displays a summary of the audit for corrupted and missing test result files. See Bad Result File for a description of the detailed tab.
Checksums	Displays a summary of the audit of the test result files checksums. See Bad Checksum for a description of the detailed tab.
Test Descriptions	Displays a summary of the audit of the test descriptions. See Bad Test Description for a description of the detailed tab.
Test Cases	Displays a summary of the audit of the exclude list. See Bad Test Cases for a description of the detailed tab.
Test Results	Displays a summary of the test results audit. To pass the audit, all tests must have passing results.
Time Stamps	Displays the date and time when the first and the last tests were run.

Bad Result File

The Bad Result File panel lists any corrupted or missing test result files.

A corrupted or missing test result file is an indication that the result file was edited.

Bad Checksum

The Bad Checksum panel lists all test result files with invalid checksums.

The result file checksums must match the reference checksums in the reference test suite. An invalid checksum is an indication that a result file was edited.

Bad Test Description

The Bad Test Description panel lists all test files with edited test descriptions.

Test descriptions must match the reference test descriptions in the reference test suite. An invalid test description is an indication that the test file was edited.

Bad Test Cases


The Bad Test Cases panel lists all tests that failed to execute the required test cases.

The test cases run must match the exclude list for the reference test suite. Tests that failed to execute the required test cases are indications that the exclude list was edited.

Audit Test Results Options

Use the Audit Test Results Options dialog box to specify the reference test suite, the audited work directory, the reference configuration, and to start the audit.

To display the Options dialog box, choose Audit > Options from the menu bar.



The Options dialog box contains the following elements:

- [Test Suite](#)
- [Work Directory](#)
- [Configuration File](#)
- [Start Audit button](#)
- [Cancel button](#)

- [Help button](#)

Test Suite

You can use the drop-down list or the chooser to specify a test suite. You can also clear a previous entry in the Test Suite field by choosing the empty line from the drop-down list. A blank field indicates a test suite is not set.

Click the  button to open the list of test suites currently loaded in the harness. You are not limited to using these tests suites. You can either choose a test suite from the list or click the  button to open the dialog box used to choose another test suite.

If you choose a reference test suite, the harness sets the entries in the work directory drop-down list to the work directories that are currently loaded and matches the specified test suite. If you have multiple test suites and work directories, specifying a test suite can simplify choosing the options.

The harness always uses the test suite associated with the work directory that you choose to audit. See Work Directory below for a description of how to choose a work directory to audit.

Work Directory

The harness audits the work directory named in the Work Directory field. A blank field indicates the work directory is not set.

You can use the drop-down list or the chooser to specify the work directory to audit. You can also clear a previous entry in the work directory field by choosing the empty line in the drop-down list.

Click the  button to open the list of work directories identified by the harness. If you choose a reference test suite, the harness only lists the work directories associated with it in the drop-down list.

You are not limited to using these work directories. You can either choose a work directory from the list or click the  button to open the dialog box used to choose another work directory.

If you choose a work directory, the harness uses the test suite associated with the work directory and sets the entries in the Configuration File drop-down list to those most recently used with the work directory.

If you do not choose a work directory, the harness uses the work directory associated with the configuration file that you specify. See Configuration File below for a description of how to choose a reference configuration file.

Configuration File

You can use the drop-down list or the chooser to specify a reference configuration file. You can also clear a previous file from the Configuration File field by choosing the empty line in the drop-down list.

A blank field indicates that the default configuration file for the chosen work directory is used. If a work directory is not chosen, you can choose a reference configuration, and the harness opens its work directory.

Click the  button to open the list of configuration files identified by the harness. The harness lists the configuration files associated with the work directory.

Choose a file from the list or click the  button to open the dialog box used in choosing a configuration file.

If you specify a configuration file, it must be associated with the work directory. If the configuration file is not associated with the work directory, the harness displays an error message without performing the audit.

Start Audit Button

After you set the audit options, click the Start Audit button to audit the work directory. The harness closes the Option dialog box and displays a message in the Audit Test Results window that it is performing the audit.

Cancel Button

Closes the Options dialog box without accepting any changes to the option fields.

Help Button

Displays online help for the Options dialog box.

Configuring a Test Run

Before the harness can execute the tests in a test suite, it requires information about how your computing environment is configured. You provide the harness with this information by loading a template (.jtm), loading an existing configuration file (.jti), creating a new configuration, or changing the values in a configuration.

Note – You can also specify configuration values from the command line when starting the harness GUI.

The quantity and scope of information required to run tests depends on the test suite. Some test suites run in diverse environments (different platforms and networks), while others run in very specific, well-defined environments. The test suite may provide a configuration interview or a template for you to use in creating a configuration for your test run. If your test suite does not provide any of these, consult the test suite documentation for directions about how you can supply the required configuration information.

This chapter contains the following topics:

- [Editing a Configuration](#) - Describes how to use the Question Mode edit a configuration.
- [Editing Quick Set Values](#) - Describes how to use the Quick Set Mode to edit the runtime values in a configuration file.
- [Creating a Configuration](#) - Describes how to create a configuration for use in running tests.
- [Saving a Configuration](#) - Describes how to save the current configuration.
- [Loading a Configuration](#) - Describes how to load an existing configuration or a template for use in running tests.
- [Using Bookmarks in Configurations](#) - Describes how to use bookmarks to simplify a configuration interview.
- [Searching a Configuration](#) - Describes how to search a configuration for characters or values.

- [Working with Multiple Configurations](#) - Describes how to use multiple configuration files to switch configurations between test runs.

Creating a Configuration

You must create a configuration for the test run if an existing configuration is not provided by the test suite or your test group.

Note – If you have an existing configuration, load it in the Test Manager (see [Loading a Configuration](#)) and then edit it (see [Editing a Configuration](#)) as required for your test run.

Before creating a configuration, if you have a template provided by your test group or by the test suite, you can load it in the Test Manager (see [Loading a Template](#)) and use it as the basis for creating a configuration. You can also create a template (see [Creating a Template](#)), if an existing template is not available, and use it as the basis for creating a configuration.

▼ Create a New Configuration

1. If you have an appropriate template provided by your test group or by the test suite, load it in the Test Manager (see [Loading a Template](#)).
You can create a template (see [Creating a Template](#)), if an appropriate, existing template is not available.
If you choose not to use a template, go to Step 2.
2. Choose Configure > New Configuration from the Test Manager menu bar or File > New Configuration from the Configuration Editor menu bar.
3. Answer the questions displayed in the Configuration Editor window.
If you are creating a configuration from a template, the values set in the template are applied to the questions.

Note – The Configuration Editor window displays questions in the center pane (see the [Question Pane](#)). Use the text box, radio button, or combo box controls located beneath the question to provide the required configuration information. After you answer each question, click the Next button to proceed to the next question. Some questions provide information and do not require an answer. In these cases, click the Next button to proceed to the next question.

You can go backward and forward to any question to review or change your answer by doing one of the following:


- Choosing a question directly from the Index pane
- Clicking the Back button, the Next button, or the Last button
 - As you move backward and forward, the Configuration Editor window saves all answers until you either save the configuration or change the answers.
 - Choose File > Save at any time to save your answers and position in a configuration file. See [Saving a Configuration](#).

4. After you complete the configuration, click the Done button to save the configuration and close the Configuration Editor window.

▼ Loading a Configuration

1. Choose Configure > Load Configuration from the Test Manager menu bar, or, if you have an open Configuration Editor window, choose File > Load Configuration from the menu bar.

The harness opens the Load Configuration dialog box.



If your test group provides an existing configuration, you can use it to run tests.

2. Locate and select the configuration file (.jti).
3. Click the Load button.

The harness loads the file and closes the Load Configuration File chooser.

If you loaded a configuration file that you must edit before running tests, use the Configuration Editor to set appropriate values for your test environment. See [Editing a Configuration](#).

▼ Editing a Configuration

1. Choose Configure > Edit Configuration in the Test Manager menu bar.

The harness opens the Configuration Editor in Question Mode and loads the current configuration.

In Question Mode, the Configuration Editor enables the Bookmarks feature. Use the Bookmarks feature to simplify an interview by displaying only questions whose answers might change. See [Using Bookmarks in Configurations](#) for the steps required to set, clear, and manage Bookmarks in a configuration. See [Question Mode](#) for detailed information about using the features of this mode to edit a configuration.

Quick Set Mode enables rapid editing of frequently changed values. If you are editing only these values, you can change to the Quick Set Mode. You can use the View menu at any time to change from one mode to the other. Because only one configuration file is loaded in the Configuration Editor at a time, any changes that you made in one mode are automatically reflected in the other mode. See [Editing Quick Set Values](#) for detailed information about using the features of this mode to edit a configuration.

2. In Question Mode, navigate to the question by one of the following means:
 - Use the Search menu to locate specific characters or character strings in the titles, questions, and answers. See [Searching a Configuration](#).
 - Choose the question directly from the Index pane.
 - Click the Back button or Next button as required to locate the question.
3. Review and change configuration values as necessary.

When you move backward and forward through the list of questions, the Configuration Editor preserves your previous answers until you change them.

4. After making all required changes to the configuration, save the changed configuration by one of the following means:
 - If you are using a configuration template or an existing configuration file to create a new configuration file, choose File > Save As from the Configuration Editor menu bar. The Configuration Editor opens a dialog box for you to use in setting the location and name of the new configuration file.
 - If you are modifying an existing configuration file used to run tests, click the Done button. The Configuration Editor saves the changes to the configuration file and closes. When the Done button is enabled, you can click it regardless of your location in the configuration.

Editing Quick Set Values


The following topics describe how values displayed in the Quick Set Mode can be changed for a test run.

- [Specifying Tests to Run](#) - Describes how to specify the individual tests or groups of tests in a test run.
- [Using Exclude Lists](#) - Describes how to specify the exclude list used for a test run.
- [Specifying Keywords](#) (Only enabled if used by the test suite) - Describes how to specify keywords to filter the tests that are run.
- [Specifying Prior Status](#) - Describes how to filter the tests that are run based on their prior results.
- [Setting Concurrency and Timeout Factor](#) - Describes how to set the concurrency and timeout values of a test run.

▼ Specifying Tests to Run

1. Click the  Quick Set Mode button on the Test Manager tool bar or choose Configure > Edit Quick Set > Tests To Run in the menu bar.

The Configuration Editor opens in Quick Set Mode.



Note – In Question Mode, use the How to Specify Tests question to specify tests that are run.

2. Click the Tests tab if it does not have focus.
3. Choose the Specify radio button.

The Configuration Editor enables the tree and the Load Test List button.

4. Use the run tree or the Load Test List button to specify the tests that are run.

See the following topics for detailed information about using the run tree or a load test list:

- [Run Tree](#)
- [Load Test List](#)

5. Click the Done button to save the configuration change.

Run Tree

In the Tests to Run pane, you can use the run tree to specify individual tests and folders for the harness to run. The Tests pane highlights all folder and test icons selected for the test run. You can make individual selections in the tree by pressing the Control key when you click an icon or name. To select a series or sequence of tests or folders, press the Shift key and then click the first and the last icon or name in the sequence.

When you select some of the tests in and under a folder, the Test pane partially highlights the folder icon. If you choose a test folder, the harness selects all tests in the test suite under that location for the test run. If you choose one or more tests, the harness selects those individual tests for the test run.

The harness walks the tree starting with the sub-branches or tests you specify and executes all tests not filtered out by the exclude list, keyword, or prior status.

Note – Restrictions are applied cumulatively. For example, you can specify the tests in a test suite, then restrict the set of tests using an exclude list, and then further restrict the set to only those tests that passed on a prior run.

Load Test List

When you click the Load Test List button, the harness opens a dialog box for you to use in locating and selecting the test list file. The test list file is a .txt file that contains a list of tests. See [Test List File Format](#) and [Creating a Test List File](#) for a detailed description of the test list file.

When the file is loaded, the harness updates the run tree to indicate the tests specified in the test list file.

Test List File Format

The format requirements of the test list file are as follows:

- Line-oriented
- Relative test paths
- Blank lines and lines beginning with the pound symbol (#) are ignored
- On all other lines, the first item (up to the first whitespace) is taken as a test name and the remainder of the line is ignored

The format of the load list file is compatible with the format of the `summary.txt` generated as part of a report.

▼ Creating a Test List File

1. Select the lines from `summary.txt` that define the tests you want to run.

Note – You can use other sources for obtaining the path names of the tests that you want to include in the test list file. On a Solaris platform, you might use awk, grep, or similar utilities to identify lines that specify the tests with failed or error results.

Example lines from `summary.txt`:

```
BigNum/compareTest.html Failed. exit code 1
BigNum>equalsTest.html Failed. exit code 1
BigNum/longConstrTest.html Failed. exit code 1
BigNum/subtractTest.html Failed. exit code 1
lists/DoublyLinkedList/appendTest.html Failed. exit code 1
lists/DoublyLinkedList>equalsTest.html Failed. exit code 1
lists/DoublyLinkedList/insertTest.html Failed. exit code 1
lists/DoublyLinkedList/removeTest.html Failed. exit code 1
lists/LinkedList/appendTest.html Failed. exit code 1
lists/LinkedList>equalsTest.html Failed. exit code 1
lists/LinkedList/insertTest.html Failed. exit code 1
```

```
lists/LinkedList/removeTest.html Failed. exit code 1
lists/SortedList>equalsTest.html Failed. exit code 1
lists/SortedList/insertTest.html Failed. exit code 1
lists/SortedList/removeTest.html Failed. exit code 1
```

2. Copy and paste the relative paths into a .txt file.

3. Remove all text that is not part of the test path.

Example lines in the .txt file:

```
BigNum/compareTest.html
BigNum>equalsTest.html
BigNum/longConstrTest.html
BigNum/subtractTest.html
lists/DoublyLinkedList/appendTest.html
lists/DoublyLinkedList>equalsTest.html
lists/DoublyLinkedList/insertTest.html
lists/DoublyLinkedList/removeTest.html
lists/LinkedList/appendTest.html
lists/LinkedList>equalsTest.html
lists/LinkedList/insertTest.html
lists/LinkedList/removeTest.html
lists/SortedList>equalsTest.html
lists/SortedList/insertTest.html
lists/SortedList/removeTest.html
```

4. Save the .txt file using a descriptive name.


Example .txt file name:

BigNum_ListsfailedTests.txt

▼ Using Exclude Lists

1. Click the  button in the Test Manager toolbar or choose Configure > Edit Quick Set > Exclude List from the Test Manager menu bar.

The Configuration Editor opens in Quick Set Mode.



Note – Exclude list files contain a list of tests in a test suite that are not run by the harness. You can also use Question Mode view to specify exclude lists.

2. Click the Exclude List tab if it does not have focus.
3. Use the buttons in the tabbed pane to set exclude list selection options and to add or remove exclude lists used to run tests in your computing environment.

See [Exclude List Selection Options](#), [Latest Exclude List](#), and [Other Exclude List](#) for a detailed description of these values and how they are used by the harness when running tests.

4. Click the Done button to save the configuration change.

Exclude List Selection Options

Use the following selections to specify the exclude list option used to run tests:

- **None** - An Exclude List is not used.
- **Initial** - Only enabled if the test suite provides an exclude list. If you choose Initial, the tests are run using the exclude list provided by the test suite.

- **Latest** - Only enabled if the test suite provides a location for updated exclude lists. If you choose Latest, additional options are displayed. See [Latest Exclude List](#) below for detailed information.
- **Other** - A custom exclude list can be used. See [Other Exclude List](#) below for detailed information.

If a complete test is added to the exclude list, the harness updates the test result status without requiring the test be rerun. However, if only a test case from a test is added to the exclude list, the harness requires that you rerun the test using the updated exclude list before updating the test result status.

Latest Exclude List

If your test suite provides a URL for the latest test suite, the harness enables the Latest exclude list option. The following table describes the text and controls displayed when you choose the Latest exclude list option.

TABLE 35 Latest Exclude List Dialog Box Contents

Text and Controls	Description
Location:	Displays the location of the exclude list specified by the test suite. This is a non-editable field.
Last updated:	Displays the date that the exclude list was last updated. This is a non-editable field.
Check For Updates Automatically	Causes the harness to automatically check the location of the exclude list and compare the date-time stamps of the remote and local exclude lists. The harness then displays a dialog box advising you of the results. If a new exclude list is available, you can choose to download it.
Every _ Days	Sets an interval for the harness to automatically check the remote location of the exclude list for updates.
Every Test Run	Causes the harness to check the remote location of the exclude list for updates before each test run.
Check Now	Causes the harness to check the remote location of the exclude list for an update.

Other Exclude List

The following table describes the buttons displayed when you choose the Other exclude list option.


TABLE 36 Other Exclude List Dialog Box Contents

Button	Description
Add	Selects an exclude list file for your test suite. As you make selections with the file chooser dialog box, they are added to the list. After you add an exclude list, you can modify the list.
Remove	Clears an item from the list. Select an item in the list and click Remove.
Move Up	Moves an item one position higher in the list. Select an item in the list and click Move Up.
Move Down	Moves an item one position lower in the list. Select an item in the list and click Move Down.

▼ Specifying Keywords

1. Click the  Quick Set Mode button on the Test Manager tool bar or choose Configure > Edit Quick Set > Keywords in the menu bar.

The Configuration Editor opens in Quick Set Mode.



Note – The harness displays this tab only if your test suite uses keywords. You can use one or more keywords to restrict the set of tests that the harness runs. In Question Mode, use the Keywords question to specify test run restrictions based on the keywords.

2. Click the Keywords tab if it does not have focus.
3. Click the Select tests that match checkbox.

The harness enables the Expression, Insert Operator, and Insert Keyword buttons.

4. Build an expression in the text field by using any logical combination of the following actions:
 - Click the Expression button to display a list of expressions that can be constructed. From the list, choose the type of expression that you are building. See [List of Expressions](#) for a description of the available types of expressions.
 - Click the Insert Keyword button to display the list of keywords provided by the test suite for use in filtering tests (this is only available if the test suite has information). From the list, choose one or more keywords used in the expression.
 - Click the Insert Operator button to display a list of logical operators that you can include to construct boolean expressions in the text field. From the list, choose an operator to include it in the expression. See [List of Logical Operators](#) for a description of the available operators.
5. Click the Done button to save the configuration change.

List of Expressions

The following table provides descriptions and examples of keyword expressions that can be constructed.

TABLE 37 Keyword Expressions

Expression	Description
Any Of	<p>Runs all tests in the test suite having any of the keywords entered in the text field.</p> <p>Example:</p> <p>A test suite uses the keyword <code>interactive</code> to identify tests that require human interaction, and <code>color</code> to identify tests that require a color display.</p> <p>To execute only the tests containing the <code>interactive</code> keyword, choose Any Of and then use the Insert Keyword button to choose the <code>interactive</code> keyword.</p>
All Of	<p>Runs all tests in the test suite having all of the keywords entered in the text field.</p> <p>Example:</p> <p>To execute only the tests containing both the <code>interactive</code> and <code>color</code> keywords, choose All Of and then use the Insert Keyword button to choose the <code>interactive</code> and <code>color</code> keyword.</p>
Expression	<p>Runs all tests in the test suite having the expression entered in the text field.</p> <p>Use the Insert Keyword and the Insert Operator buttons to construct a Boolean expression in the text field. Keywords stand as Boolean predicates that are true if, and only if, the keyword is present in the test being considered. A test is accepted if the overall value of the expression is true. All other tests are rejected by the restriction.</p> <p>Example:</p> <p>A test suite uses the keyword <code>interactive</code> to identify tests that require human interaction, and <code>color</code> to identify tests that require a color display.</p> <p>To execute only the tests with the <code>color</code> keyword that do not also contain the <code>interactive</code> keyword, choose Expression and then use the Insert Keyword button to choose the <code>color</code> keyword, the Insert Operator button to choose the <code>!</code> operator, and the Insert Keyword button to choose the <code>interactive</code> keyword.</p>

List of Logical Operators

Logical operators are only available when Expression is selected in the list of expressions. The following table provides descriptions and examples of logical operators that can be used to build keyword expressions. The precedence column

indicates the order in which the expression is resolved. Expressions in parentheses are evaluated first, with nested parentheses being evaluated from the innermost parentheses outward.


TABLE 38 Keyword Operators

Logical Operator	Precedence	Description
() group	1	<p>Used to create groups of expressions.</p> <p>Example:</p> <p>A test suite uses the keyword <code>interactive</code> to identify tests that require human interaction and <code>color</code> to identify tests that require a color display.</p> <p><code>!(interactive&color)</code></p> <p>The harness will exclude tests that include both keywords.</p>
! not	2	<p>Logical not. Used to exclude tests containing the expression.</p> <p>Example:</p> <p>A test suite uses the keyword <code>interactive</code> to identify tests that require human interaction and <code>color</code> to identify tests that require a color display.</p> <p><code>!interactive&!color</code></p> <p>The harness will exclude tests that include either keyword.</p>
& and	3	<p>Logical and. Used to combine expressions.</p> <p>Example:</p> <p>A test suite uses the keyword <code>interactive</code> to identify tests that require human interaction and <code>color</code> to identify tests that require a color display.</p> <p><code>interactive&color</code></p> <p>The harness will only choose tests that include both keywords.</p>
or	4	<p>Logical or. Used to specify either of two expressions.</p> <p>Example:</p> <p>A test suite uses the keyword <code>interactive</code> to identify tests that require human interaction and <code>color</code> to identify tests that require a color display.</p> <p><code>interactive color</code></p> <p>The harness will only choose tests that include either keyword.</p>

▼ Specifying Prior Status

1. Click the  Quick Set Mode button on the Test Manager tool bar or choose Configure > Edit Quick Set > Prior Status in the menu bar.

The Configuration Editor opens in Quick Set Mode and displays the Prior Status tab.



Note – In Question Mode, use the Status question to specify prior status used to restrict the set of tests that are run.

2. Check the Select tests that match option.

The Configuration Editor enables the prior status check boxes.

3. Check the one or more of the prior status conditions.

See [Prior Status Selections](#) for detailed descriptions of the available choices and how the harness uses them to filter the tests that are run.

4. Click the Done button to save the configuration change.

Prior Status Filter Selections

By choosing Select tests that match, you can run tests with restrictions based on their result from a prior test run. The following table describes the available Prior Status filter selections.

TABLE 39 Using Prior Status as a Filter

Prior Status Filter	Action
Passed	Selects tests with passing results the last time the test was executed.
Failed	Selects tests with failed results the last time the test was executed.
Error	Selects tests that the harness could not execute the last time it was included in a test run.
Not Run	Selects tests without results in the current work directory.

Prior status is evaluated on a test-by-test basis using information stored in the result files (.jtr) that are written in the work directory. Unless overridden by a test suite, a result file is written in the work directory for every test that is executed. When you change work directories between test runs, the result files in the previous work directory are no longer used and, if the new work directory is empty, the harness behaves as though each test in the test suite was not run.

You can also use the Prior Status setting in combination with the Current Configuration view filter to display only those test and folder status icons that match the specified prior status. The test tree displays all other tests and folders as

gray, filtered out  folder and  test icons. During a test run, when a test result no longer matches the prior status filter, the test tree changes the test and folder

icons to gray, filtered out  folder and  test icons.


For example, if you only want to monitor tests in a test suite that had failed results you would set the Prior Status filter to Any Of Failed and repeat the test run. As tests pass, the test tree changes their icons from failed to filtered out, indicating that they no longer match the Prior Status filter Any Of Failed.

Note – It is often useful to choose all of the status values except Passed for the first few test runs, then refine the filtering to reduce the number of tests in subsequent runs.

▼ Setting Concurrency and Timeout Factor

1. Click the  Quick Set Mode button on the Test Manager tool bar, choose Configure > Edit Quick Set > Concurrency, or choose Configure > Edit Quick Set > Timeout Factor in the menu bar.

The Configuration Editor opens in Quick Set Mode.



Note – You can also use the Configuration Editor window in Question Mode to specify the concurrency and the timeout factor.

2. Click the Execution tab if it does not have focus.
3. Use the text fields in the tabbed pane to set the concurrency and the timeout factor values used to run tests in your computing environment.

See [Concurrency](#) and [Time Factor](#) for a detailed description of these values and how they are used by the harness when running tests.

4. Click the Done button to save the configuration change.

Concurrency

The harness can run tests concurrently. If you are running the tests on a multiprocessor computer or are using multiple agents on a test system, concurrency can reduce the time required to run tests. For detailed information about using agents to run tests, refer to your test suite documentation and to the *JavaTest Harness Agent User's Guide* if it is provided by the test suite.

When using multiple agents to run tests, the concurrency value must not exceed the number of agents. If the concurrency value exceeds the total number of available agents, an error will occur in the test run.

If you have unexpected test failures, run the tests again, one at a time. Some test suites may not work correctly if you run tests concurrently. The default range of values used by the harness is from 1 to 50.

For your first test run, leave this field set to 1. After the tests run properly, you can increase this value. Unless your test suite restricts concurrency, the maximum number of threads specified by the concurrency command is 50. See your test suite documentation for additional information about using concurrency values greater than 1.

This field is disabled for some test suites.

Time Factor

To prevent a stalled test from stopping a test run, most test suites set a timeout limit for each test. The timeout limit is the amount of time that the harness waits for a test to complete before moving on to the next test.

If you are running the tests on a particularly slow CPU or slow network, you can change the time limit by specifying a floating point value in the time factor field. Each test's timeout limit is multiplied by the time factor value. The default range of values used by the harness is from 0.1 to 100.0.

Note – In the Time Factor field, the harness uses the form of floating point values that is specific to the locale in which it is run. For example, if your locale uses floating point values in the form of x, x , harness uses that form of floating point value in the Time Factor field. In setting the timeout factor in the following example, specify values of 2, 0 and 0, 5 if your locale uses floating point values in the form of x, x .

Example:

If you specify a value of `2.0`, the timeout limit for tests with a basic 10-minute time limit becomes 20 minutes. Specifying a value of `0.5` for tests with a 10-minute limit produces a 5-minute timeout limit.

At first, use the default value of `1.0` to run tests and then, if necessary, increase the value. The actual timeout calculation for any particular test suite might vary.

▼ Saving a Configuration

If you use different configurations to run a test suite, see [Working with Multiple Configurations](#).

Using Bookmarks in Configurations

In Question Mode, you can use Bookmarks to restrict the set of questions displayed in the Configuration Editor (Bookmarks are not used in Quick Set Mode).

Bookmarks are persistent and are saved in the `.jti` file, and reloaded when the configuration is used again. When bookmarks are disabled, they are preserved in program memory but cannot be manipulated.

▼ Set Bookmarks for Specific Questions

1. Click the Bookmarks > Enable Bookmarks check box in the menu bar.
2. Click a question in the Configuration Editor.
3. Set a bookmark for the highlighted question by performing one of the following actions:
 - Click to the left of the highlighted question text.
 - Choose Bookmarks > Mark Current Question in the menu bar.
 - Right click the highlighted question and choose the Mark Current Question menu item in the pop-up menu.

▼ Display Questions With Bookmarks

- Click the Bookmarks > Show Only Bookmarked Questions checkbox in the menu bar.

The Configuration Editor displays bookmarked questions in the following manner:

- The first question in the interview is displayed.
- Questions with bookmarks are displayed.
- If the interview is complete (all questions have valid answers) the final question is displayed.
- If the interview is incomplete (one or more questions have invalid or incomplete answers), the questions from the last marked question to the first question with an invalid or incomplete answer are displayed.
- Sequences of questions not described by a previous category are grouped and represented by three dashes (---) in the list. These groups can be opened to display the complete sequence of questions.

▼ Open Groups of Questions

1. Click the --- section in the list of questions.
1. Click a question in the list of questions.
2. Click the Bookmarks > Clear Answers to Bookmarked Questions menu item from the menu bar.

▼ Clear the Value of a Specific Question

1. Click the question in the list of questions.
2. Click the Bookmarks > Clear Answer For Current Question menu item or right click the highlighted question and choose Clear Answer For Current Question from the pop-up menu.

▼ Remove All Bookmarks

- Choose the Bookmarks > Remove Bookmarks menu item.

The configuration list reverts to the full configuration list.

▼ Remove a Bookmark From a Question

1. Click the question in the list of questions.
2. Click the Bookmarks > Unmark Current Question menu item or right click the highlighted question and choose Unmark Current Question menu item from the pop-up menu.

Searching a Configuration

When using the Configuration Editor in Question Mode, you can locate and display the panes containing a specific character string. The harness can search titles, questions, and answers for matching characters. It does not search the More Info.


▼ Search for Characters in Configurations

1. Click the  Question Mode button on the Test Manager tool bar or choose Configure > Edit Configuration in the menu bar.

The Configuration Editor opens in Question mode.

2. Choose Search > Find.

The harness displays the Find Question dialog box.



3. Enter the search character string in the String field.

See the String field description in [Search Criteria](#).

4. Choose the search location from the Where drop down list.

See the Where description in [Search Criteria](#).

5. Choose any required search options.

See the Options descriptions in [Search Criteria](#).

1. Click the Find button to search for the character string.

To repeat the search, either click the Find button or use the Search > Find Next menu item from the Configuration Editor menu bar.

2. Click the Close button to dismiss the dialog box.

Search Criteria

The following table describes the search criteria used in the Find Question dialog box.

TABLE 40 Find Question Dialog Box Search Criteria

Item	Description
String	Enter the character string that you are trying to find.
Where	Choose where you want to search: <ul style="list-style-type: none">• In titles• In text of questions• In answers• Anywhere
Options: Consider case	Specifies that the search pattern match the case of the characters in the Find text field.
Options: Whole words	Specifies that the search pattern only match whole words from the Find text field.

Working with Multiple Configurations

In some testing situations it is useful to use separate configuration files to switch between different configurations for different test runs. For example, one configuration could select automated tests and another could select interactive tests.

Prior to running tests, use the Configure menu to load the required configuration file. See [Loading a Configuration](#) for detailed information. These configuration files can be loaded from a central resource provided by your test group. See your test group for the name and location of the configuration files.

If your group does not provide an existing set of configuration files, you can create them by using the Configuration Editor to edit an existing configuration and then save each variation to a file name of your choosing. See [Editing a Configuration](#) for detailed information.

You can save these configuration files anywhere in your file system. Generally, however, the work directory should not be used to save configuration files. Clearing the work directory would delete the configuration file.

After these configuration files are created, they can be used by your test group to run tests.

Creating and Editing Templates

The harness provides users with the [optional](#) ability to create and edit templates that can be used to run tests on multiple test systems or test platform.

Note – Your test suite might not enable creating or editing templates. The menu items and features described here [will not appear in your user interface](#) if your test suite does not support templates.

For example, if your test suite enables creating and editing templates and your test group uses a central location to provide and manage the resources required to run tests (the test suite, report directories, configuration files, or the harness), you can create a template that contains all known configuration values required by the test group to run tests. Each user can load the template from the central site, provide only those values unique to their test environment or test run, and run their tests using their completed configuration.

See [Creating a Template](#) for a detailed description of the process used to create a template.

See [Editing a Template](#) for a detailed description of the process used to change the contents of a template.

In addition to providing users with partially completed configurations, templates can further simplify the process of creating and maintaining configurations through the use of the following features:

- Bookmarks
- Propagation

An optional feature of templates is the ability to propagate (inherit) template updates to all configurations based on that template. When the test suite developer enables template propagation, the harness checks for template updates when a user does any of the following:

- Starts a test run.

- Opens a work directory.
- Loads a configuration.

For a configuration to receive template updates, the test suite developer must enable propagation in both the configuration and its template.

▼ Creating a Template

1. Choose Configure > New Template from the Test Manager menu bar.
2. Answer the questions displayed in the Template Editor.

The Template Editor displays questions in the center pane (the Question Pane). After answering a question, click the Next button to proceed to the next question.

3. Choose File > Save As from the menu bar and save the template with a relevant name.

Template file names are automatically appended with a `.jtm` extension.

Note – Changes to a template propagate to configurations based on the template *only* if propagation is enabled in both the template and the derived configurations.

Editing a Template

The Template Editor provides the following two modes of displaying and editing the questions and values in a template.

See [Question Mode](#) for detailed information about using the features of this editing mode.

- Question Mode - Enables editing of all template questions.
- Quick Set Mode - Enables rapid editing of a limited set of template questions.

Quick Set Mode filters out all test suite specific questions and displays a limited

set of general questions whose values are often changed from test run to test run. In this editing mode, the Template Editor creates logical groupings of the values and displays them in tab form for easy user navigation and access.

▼ Editing in Question Mode

1. If you are editing the current template (named at the bottom of the Test Manager) choose Configure > Edit Template in the Test Manager menu bar, otherwise choose either Configure > Load Template or Configure > Load Recent Template.

If you are editing the current template (named at the bottom of the Test Manager), the harness opens the Template Editor and loads the template. Go to step 3.

If you are editing a different template, the harness displays the Load Template dialog box.

2. Use the dialog box to locate and load the template.

The harness opens the Template Editor and displays the template in Question Mode.

3. Use Question Mode to change the values of questions in the template.
4. Click Done to save the changes and close the Template Editor.

You can use the View menu at any time to change from one mode to the next. Because there is only one template file loaded in the Template Editor at a time, when you change modes during an editing session, any changes made in one mode are automatically reflected in the other.

If a configuration is attached to the edited template, the harness opens a Template updated dialog box that enables you to review the changes and to accept, reject, or postpone having the changes propagated to the attached configuration. See [Resolving Configuration-Template Conflicts](#) for a description of the dialog box and the choices available to the user.

▼ Editing in Quick Set Mode

1. If you are editing the current template (named at the bottom of the Test Manager) choose Configure > Edit Template in the Test Manager menu bar, otherwise choose either Configure > Load Template or Configure > Load Recent Template.

If you are editing the current template (named at the bottom of the Test Manager), the harness opens the Template Editor and loads the template. Go to step 3.

If you are editing a different template, the harness displays the Load Template dialog box.

2. Use the dialog box to locate and load the template.

The harness opens the Template Editor and displays the template in Question Mode.

3. Choose View > Quick Set Mode in the Template Editor menu bar.

The harness displays the Template Editor in Quick Set Mode.

4. Set the quick set values by using the following tabs:

- [Tests](#) - Use this tab to edit the default set of tests that a user can run in this configuration.
- [Exclude List](#) - (Optional) Use this tab to edit the default list of tests that are excluded from a test run using this configuration.
- [Keywords](#) - (Optional) Use this tab to edit the default keywords and expressions used in this configuration to run tests.
- [Prior Status](#) - Use this tab to edit the default restrictions on tests that are run by using their status from the previous test run.
- [Execution](#) - (Optional) Use this tab to edit the default concurrency and timeout factor values used in the configuration for running tests.


5. Click Done to save the changes and close the Template Editor.

You can use the View menu at any time to change from one mode to the next. Because there is only one template file loaded in the Template Editor at a time, when you change modes during an editing session, any changes made in one mode are automatically reflected in the other.

If a configuration is attached to the edited template, the harness opens a Template updated dialog box that enables you to review the changes and to accept, reject, or postpone having the changes propagated to the attached configuration. See [Resolving Configuration-Template Conflicts](#) for a description of the dialog box and the choices available to the user.

▼ Changing Tests to Run

1. Choose View > Quick Set Mode from the Template Editor menu bar.
2. Click the Tests tab in the Template Editor.



4. In Quick Set Mode, choose Specify to enable the Template Editor test tree and the Load Test List button.

In Question Mode, use the How to Specify Tests question to specify whether to use the test tree or a test list.

5. Use the test tree or a test list to specify the tests that are run.

See the following topics for detailed information about using the test tree or load list to specify tests:

[Specifying Tests in the Test Tree](#)

[Loading a Test List](#)

6. Change additional template settings or click the Done button to save the changes in the template.

If you are creating a new template for these changes, instead of clicking the Done button, choose File > Save As from the Template Editor menu bar and save the template with a relevant name.

Specifying Tests in the Test Tree

In the Template Editor test tree (not the Test Manager test tree) you can choose individual tests and folders of tests for the harness to run. The harness walks the test tree starting with the sub-branches or tests you specify and executes all tests not filtered out by the exclude list, keyword, or prior status.

Restrictions are applied cumulatively. For example, you can specify the tests in a test suite, then restrict the set of tests using an exclude list, and then further restrict the set to only those tests that passed on a prior run.

If you choose a test folder, the harness selects all tests in the test suite under that location for the test run.

If you choose one or more tests, the harness selects those individual tests for the test run.

The Tests pane highlights all folder and test icons selected for the test run. You can make individual selections in the test tree by pressing the Control key when you click an icon or name in the test tree.

To select a series or sequence of tests or folders, press the Shift key and then click the first and the last icon or name in the sequence.

When you select some (but not all) of the tests in and under a folder, the Test pane partially highlights the folder icon.

▼ Loading a Test List

1. Click the Load Test List button.
2. Use the dialog box to locate and select a test list file.

See *Test List File Format* for a detailed description of a test list file.

3. When the file is loaded, the test tree is updated to indicate the tests that have been specified.

Test List File Format

A test list is a .txt file containing a list of tests to run. See [Creating a Test List File](#) for a detailed description of the test list file. The format requirements of the test list file are as follows:

- Line-oriented
- Relative test paths
- Blank lines and lines beginning with the pound symbol (#) are ignored

- On all other lines, the first item (up to the first whitespace) is taken as a test name and the remainder of the line is ignored

The format of the load list file is the same as the format of the `summary.txt` generated as part of a report.

▼ Creating a Test List File

1. Select the lines from `summary.txt` that define the tests you want to run.

Note – You can use other sources for obtaining the path names of the tests that you want to include in the test list file. On a Solaris platform, you might use `awk`, `grep`, or similar utilities to identify lines that specify the tests with failed or error results.

Example lines from `summary.txt`:

1.

```
BigNum/compareTest.html Failed. exit code 1
    BigNum>equalsTest.html Failed. exit code 1
    BigNum/longConstrTest.html Failed. exit code 1
    BigNum/subtractTest.html Failed. exit code 1
    lists/DoublyLinkedList/appendTest.html Failed. exit code 1
    lists/DoublyLinkedList>equalsTest.html Failed. exit code 1
    lists/DoublyLinkedList/insertTest.html Failed. exit code 1
    lists/DoublyLinkedList/removeTest.html Failed. exit code 1
    lists/LinkedList/appendTest.html Failed. exit code 1
    lists/LinkedList>equalsTest.html Failed. exit code 1
    lists/LinkedList/insertTest.html Failed. exit code 1
    lists/LinkedList/removeTest.html Failed. exit code 1
    lists/SortedList>equalsTest.html Failed. exit code 1
    lists/SortedList/insertTest.html Failed. exit code 1
    lists/SortedList/removeTest.html Failed. exit code 1
```
2. Copy and paste the relative paths into a `.txt` file.
3. Remove all text from the path names that is not part of the test path.
4. Example lines in the `.txt` file:

```
BigNum/compareTest.html
BigNum>equalsTest.html
BigNum/longConstrTest.html
BigNum/subtractTest.html
lists/DoublyLinkedList/appendTest.html
lists/DoublyLinkedList>equalsTest.html
lists/DoublyLinkedList/insertTest.html
lists/DoublyLinkedList/removeTest.html
```

```
lists/LinkedList/appendTest.html  
lists/LinkedList>equalsTest.html  
lists/LinkedList/insertTest.html  
lists/LinkedList/removeTest.html  
lists/SortedList>equalsTest.html  
lists/SortedList/insertTest.html  
lists/SortedList/removeTest.html
```


5. Save the .txt file using a descriptive name.

Example .txt file name:

BigNum_ListsfailedTests.txt

▼ Adding or Removing Exclude Lists

1. Choose View > Quick Set Mode from the Template Editor menu bar.
2. Click the Exclude List tab in the Template Editor.



4. Add or remove exclude lists in the template as required.

Note – Exclude list files contain a list of tests in a test suite that are not run by the harness. See [Exclude List Pane](#) for a description of this pane.

5. Change additional template settings or click the Done button to save the changes in the template.

If you are creating a new template for these changes, instead of clicking the Done button, choose File > Save As from the Template Editor menu bar and save the template with a relevant name.

Exclude List Pane

Use the following to change the exclude list used to run tests:

- **None** - An Exclude List is not used.
- **Initial** - Only enabled if the test suite provides an exclude list. If you choose Initial, the tests are run using the exclude list provided by the test suite.
- **Latest** - Only enabled if the test suite provides a location for updated exclude lists. If you choose Latest, additional options are displayed. See [Latest Exclude List](#) below for detailed information.
- **Other** - A custom exclude list can be used. See [Other Exclude List](#) below for detailed information.

If a complete test is added to the exclude list, the harness updates the test result status without requiring the test be rerun. However, if only a test case from a test is added to the exclude list, the harness requires that you rerun the test using the updated exclude list before updating the test result status.

Latest Exclude List

If your test suite provides a URL for the latest test suite, the harness enables the Latest exclude list option. The following table describes the text and controls displayed when you choose the Latest exclude list option.

TABLE 41 Latest Exclude List Dialog Box Contents

Text and Controls	Description
Location	Displays the location of the exclude list specified by the test suite. This is a non-editable field.
Last updated	Displays the date that the exclude list was last updated. This is a non-editable field.
Check For Updates Automatically	Causes the harness to automatically check the location of the exclude list and compare the date-time stamps of the remote and local exclude lists. The harness then displays a dialog box advising you of the results. If a new exclude list is available, you can choose to download it.
Every _ Days	Sets an interval for the harness to automatically check the remote location of the exclude list for updates.
Every Test Run	Causes the harness to check the remote location of the exclude list for updates before each test run.
Check Now	Causes the harness to check the remote location of the exclude list for an update.

Other Exclude List

The following table describes the buttons displayed when you choose the Other exclude list option.


TABLE 42 Other Exclude List Dialog Box Contents

Button	Description
Add	Selects an exclude list file for your test suite. As you make selections with the file chooser dialog box, they are added to the list. After you add an exclude list, you can modify the list.
Remove	Clears an item from the list. Select an item in the list and click Remove.
Move Up	Moves an item one position higher in the list. Select an item in the list and click Move Up.
Move Down	Moves an item one position lower in the list. Select an item in the list and click Move Down.

▼ Editing Keywords and Expressions

1. Choose View > Quick Set Mode from the Template Editor menu bar.
2. Click the Keywords tab in the Template Editor.

The JT harness displays this tab only if your test suite uses keywords.



4. Use the Expression, Insert Operator, and Insert Keyword buttons to build an expression in the text field by using any logical combination of the following actions:
 - Click the Expression button to display a list of expressions that can be constructed. From the list, choose the type of expression that you are building.
 - Click the Insert Keyword button to display the list of keywords provided by the test suite for use in filtering tests (this is only available if the test suite has information). From the list, choose the keywords used in the expression.
 - Click the Insert Operator button to display a list of operators that you can use to construct boolean expressions in the text field. From the list, choose the operator used in the expression.

See Keyword Expressions for descriptions and examples of keyword expressions that can be constructed.

5. Change additional template settings or click the Done button to save the changes in the template.

Keyword Expressions

The following table provides descriptions and examples of keyword expressions that can be constructed.

TABLE 43 Keyword Expressions

Expression	Description
Any Of	<p>Runs all tests in the test suite having any of the keywords entered in the text field.</p> <p>Example:</p> <p>A test suite uses the keyword <code>interactive</code> to identify tests that require human interaction, and <code>color</code> to identify tests that require a color display.</p> <p>To execute only the tests containing the <code>interactive</code> keyword, choose Any Of and then use the Insert Keyword button to choose the <code>interactive</code> keyword.</p>
All Of	<p>Runs all tests in the test suite having all of the keywords entered in the text field.</p> <p>Example:</p> <p>To execute only the tests containing both the <code>interactive</code> and <code>color</code> keywords, choose All Of and then use the Insert Keyword button to choose the <code>interactive</code> and <code>color</code> keyword.</p>
Expression	<p>Runs all tests in the test suite having the expression entered in the text field.</p> <p>n</p> <p>Use the Insert Keyword and the Insert Operator buttons to construct a Boolean expression in the text field. Keywords stand as Boolean predicates that are true if, and only if, the keyword is present in the test being considered. A test is accepted if the overall value of the expression is true. All other tests are rejected by the restriction.</p> <p>Example:</p> <p>A test suite uses the keyword <code>interactive</code> to identify tests that require human interaction, and <code>color</code> to identify tests that require a color display.</p> <p>To execute only the tests with the <code>color</code> keyword that do not also contain the <code>interactive</code> keyword, choose Expression and then use the Insert Keyword button to choose the <code>color</code> keyword, the Insert Operator button to choose the <code>!</code> operator, and the Insert Keyword button to choose the <code>interactive</code> keyword.</p>

List of Logical Operators

Logical operators are only available when Expression is selected in the list of expressions. The following table provides descriptions and examples of logical operators that can be used to build keyword expressions. The precedence column


indicates the order in which the expression is resolved. Expressions in parentheses are evaluated first, with nested parentheses being evaluated from the innermost parentheses outward.

TABLE 44 Keyword Operators

Logical Operator	Precedence	Description
() group	1	<p>Used to create groups of expressions.</p> <p>Example:</p> <p>A test suite uses the keyword <code>interactive</code> to identify tests that require human interaction and <code>color</code> to identify tests that require a color display.</p> <pre>!(interactive&color)</pre> <p>The harness will exclude tests that include both keywords.</p>
! not	2	<p>Logical not. Used to exclude tests containing the expression.</p> <p>Example:</p> <p>A test suite uses the keyword <code>interactive</code> to identify tests that require human interaction and <code>color</code> to identify tests that require a color display.</p> <pre>!interactive&!color</pre> <p>The harness will exclude tests that include either keyword.</p>
& and	3	<p>Logical and. Used to combine expressions.</p> <p>Example:</p> <p>A test suite uses the keyword <code>interactive</code> to identify tests that require human interaction and <code>color</code> to identify tests that require a color display.</p> <pre>interactive&color</pre> <p>The harness will only choose tests that include both keywords.</p>
or	4	<p>Logical or. Used to specify either of two expressions.</p> <p>Example:</p> <p>A test suite uses the keyword <code>interactive</code> to identify tests that require human interaction and <code>color</code> to identify tests that require a color display.</p> <pre>interactive color</pre> <p>The harness will only choose tests that include either keyword.</p>

▼ Editing Prior Status Settings

1. Choose `View > Quick Set Mode` from the Template Editor menu bar.
2. Click the Prior Status tab in the Template Editor.



4. Change the prior status settings in the template as required.

See [Prior Status Pane](#) for a description of this pane.

5. Change additional template settings or click the Done button to save the changes in the template.

If you are creating a new template for these changes, instead of clicking the Done button, choose File > Save As from the Template Editor menu bar and save the template with a relevant name.

Prior Status Pane

By choosing Select tests that match, you can run tests with restrictions based on their result from a prior test run. The following table describes the available Prior Status filter selections.


TABLE 45 Using Prior Status as a Filter

Prior Status	Action
Passed	Selects tests that passed the last time the test was executed.
Failed	Selects tests that failed the last time the test was executed.
Error	Selects tests that the harness could not execute the last time it was included in a test run.
Not Run	Selects tests without results in the current work directory.

Prior status is evaluated on a test-by-test basis using information stored in the result files (.jtr) that are written in the work directory. Unless overridden by a test suite, a result file is written in the work directory for every test that is executed. When users change work directories between test runs, the result files in the previous work directory are no longer used and, if the new work directory is empty, the harness behaves as though each test in the test suite was not run.

▼ Editing Concurrency and Timeout Factor

1. Choose View > Quick Set Mode from the Template Editor menu bar.
2. Click the Execution tab in the Template Editor.



4. Change the values in the Concurrency and Time Factor fields as required.

See [Concurrency](#) and [Time Factor](#) for detailed descriptions of these settings.

5. Change additional template settings or click the Done button to save the changes in the template.

If you are creating a new template for these changes, instead of clicking the Done button, choose File > Save As from the Template Editor menu bar and save the template with a relevant name.

Concurrency

The harness can run tests concurrently. If users run tests on a multiprocessor computer or are using multiple agents on a test system, concurrency can reduce the time required to run tests. For detailed information about using agents to run tests, refer to the test suite documentation and to the *JavaTest Harness Agent User's Guide* if it is provided by the test suite.

When using multiple agents to run tests, the concurrency value must not exceed the number of agents. If the concurrency value exceeds the total number of available agents, an error will occur in the test run.

The default range of values used by the harness is from 1 to 50. If unexpected test failures occur, run the tests again, one at a time. Some test suites may not work correctly if tests run concurrently.

For the first test run, set the value in this field to 1. After the tests run properly, incrementally increase this value. Unless the test suite restricts concurrency, the maximum *number* of threads specified by the `concurrency` command is 50. See the test suite documentation for additional information about using concurrency values greater than 1.

This field is disabled for some test suites.

Time Factor

To prevent a stalled test from stopping a test run, most test suites set a timeout limit for each test. The timeout limit is the amount of time that the harness waits for a test to complete before moving on to the next test.

If users run tests on a slow CPU or slow network, change the time limit by specifying a floating point value in the time factor field. Each test's timeout limit is multiplied by the time factor value. The default range of values used by the harness is from 0.1 to 100.0.

Note – In the Time Factor field, the harness uses the form of floating point values that is specific to the locale in which it is run. For example, if your locale uses floating point values in the form of x, x , harness uses that form of floating point value in the Time Factor field. In setting the timeout factor in the following example, specify values of $2, 0$ and $0, 5$ if your locale uses floating point values in the form of x, x .


Example:

If you specify a value of 2.0 , the timeout limit for tests with a basic 10-minute time limit becomes 20 minutes. Specifying a value of 0.5 for tests with a 10-minute limit produces a 5-minute timeout limit.

At first, use the default value of 1.0 to run tests and then, if necessary, increase the value. The actual timeout calculation for any particular test suite might vary.


Resolving Configuration-Template Conflicts

When the harness detects a conflict between a configuration and its template, it displays a Template update conflict dialog box.



By default, any change to a template is considered a Conflict and is listed in the Conflicts tab. Configuration users get to choose whether to accept the new template value, reject the value, or postpone deciding.

A test suite can also declare a template question to be auto-updating. If a user changes an auto-updating value in the template, the harness replaces the corresponding property in the attached configuration. The updated value is listed on the Updates tab.



A user cannot refuse to accept an auto-updating value.

Choose a dialog button based on the following guidelines:

- **Change Now** - Click this button if you want the new template values to overwrite the corresponding configuration values.
- **Don't Change** - Click this button if you want the new template values to be ignored.
- **Remind Me Later** - Click this button if you want to defer the conflict resolution until the next time the harness checks for updates.

Setting Bookmarks

You can use Bookmarks to restrict the set of questions displayed when a user loads the template in a Configuration Editor. This feature enables you to reduce the visible length and complexity of a configuration interview by only displaying the questions that a user must answer before running tests.

Bookmarks are persistent and are saved in the `.jtm` file. If bookmarks are disabled by a user, they remain in program memory but cannot be manipulated.

▼ Set Bookmarks for Specific Questions

1. Click the Bookmarks > Enable Bookmarks check box in the menu bar.
2. Click a question in the Template Editor.
3. Set a bookmark for the highlighted question by performing one of the following actions:
 - Click to the left of the highlighted question text.
 - Choose Bookmarks > Mark Current Question in the menu bar.
 - Right click the highlighted question and choose the Mark Current Question menu item in the pop-up menu.

▼ Display Questions With Bookmarks

- Click the Bookmarks > Show Only Bookmarked Questions checkbox in the menu bar.

The Template Editor displays bookmarked questions in the following manner:

- The first question in the interview is displayed.
- Questions with bookmarks are displayed.
- If the interview is complete (all questions have valid answers) the final question is displayed.
- If the interview is incomplete (one or more questions have invalid or incomplete answers), the questions from the last marked question to the first question with an invalid or incomplete answer are displayed.
- Sequences of questions not described by a previous category are grouped and represented by three dashes (---) in the list of questions. These groups can be opened to display the complete sequence of questions.

▼ Open Groups of Questions

Groups of hidden questions without bookmarks are represented by three dashes (---) in the list of questions.

1. Click the --- section in the list.
2. Click the Bookmarks > Open --- Group menu item from the menu bar or right click the highlighted --- section and choose Open --- Group menu item from the pop-up menu.

▼ Close Groups of Questions

1. Click the question in the list.
2. Click the Bookmarks > Close --- Group menu item from the menu bar or right click the highlighted --- section and choose Close --- Group menu item from the pop-up menu.

▼ Clear the Values of All Questions With Bookmarks

1. Click a question in the question list.
2. Click the Bookmarks > Clear Answers to Bookmarked Questions menu item from the menu bar.

▼ Clear the Value of a Specific Question

1. Click the question in the list.
2. Click the Bookmarks > Clear Answer For Current Question menu item or right click the highlighted question and choose Clear Answer For Current Question from the pop-up menu.

▼ Remove All Bookmarks

- Choose Bookmarks > Remove Bookmarks.

The list of questions reverts to the full list.


▼ Remove a Bookmark From a Question

1. Click the question in the question list.
2. Click the Bookmarks > Unmark Current Question menu item or right click the highlighted question and choose Unmark Current Question menu item from the pop-up menu.

Using Template Search

When using the Template Editor in Question Mode, you can locate and display the panes containing a specific character string by choosing Search > Find. The Find Question dialog box is used in locating and displaying a specified character string.

The editor can search titles, questions, and answers for matching characters. It does not search the More Info.



The following table describes the search criteria used in the Find Question dialog box.

TABLE 46 Find Question Dialog Box Search Criteria

Item	Description
String	Enter the character string that you are trying to find.
Where	Choose where you want to search: In titles In text of questions In answers Anywhere
Options: Consider case	Specifies that the search pattern match the case of the characters in the Find text field.
Options: Whole words	Specifies that the search pattern only match whole words from the Find text field.

Click the Find button to search for the character string.

To repeat the search, either click the Find button again or use the Search > Find

Next menu item from the Template Editor menu bar.
Click the Help button to display context-sensitive help.


▼ Loading a Template

1. Choose Configure > Load Template from the Test Manager menu bar.

The harness opens a Load Template dialog box containing a path field with a Browse button and a navigation area that displays the file name, the template name (contained in the template), and the template description (contained in the template).

The Path field sets the starting location for the directories and files displayed in the navigation area.

The navigation area displays the directories and template files (if any) in the location set in the Path field. Only template files are displayed in the navigator area. Other files are hidden.



2. Use the icons in the dialog box to navigate to the location of the template.

The Path text field in the dialog box displays the location for the list of files displayed in the dialog box.

3. Click the template icon and the Load button.

The harness loads the template. If the template is not correct for the test suite, the harness displays an error dialog box and closes without loading the template.

Running Tests

In the Test Manager, you can use the Run Tests menu or the toolbar button to start a test run of the tests specified in your current configuration. See [Test Manager Tool](#) for a description of the Run Tests menu and the tool bar buttons. See [Configuring a Test Run](#) for a description of how to use the Configuration Editor to specify configuration information used to run tests.

You can also use the test tree pop-up menu to start a test run of one or more tests selected from the test tree. See [Test Tree Pop-up Menu](#) for a description of how to use the test tree pop-up menu to run individual tests in a test tree.

Note – If you do not want to use the Test Manager to run tests, you can use the command line. See Command-Line Summary in the *Command-Line Interface User's Guide* for information about running tests from the command line.

The harness saves all test results after running tests but does not automatically generate reports of test results. You must generate test reports from the Test Manager or from the command line. See [Generating and Viewing Reports](#) for detailed information about reports.

If you use the All Tests view filter and begin a test run, the harness displays an advisory dialog box. Using the All Test view filter displays the results of all tests in a test suite regardless of whether or not they are included in the test run.

You can choose to disable the dialog box by setting harness Preferences, by choosing a different view filter, or by using the check box in the dialog to stop the dialog from being displayed in the future.

This chapter contains the following topics, presented in a sequence that you can use when running tests:

- **Starting a Test Run** - Describes how to use the Test Manager to start a test run using the current configuration.
- **Monitoring a Test Run** - Describes how to use the Test Manager (including the use of the Log Viewer) to monitor a test run.

- **Monitoring Agents** - Describes how to use the Agent Monitor tool to monitor agent activity during a test run.
- **Stopping a Test Run** - Describes how to use the Test Manager to stop a test run.
- **Troubleshooting a Test Run** - Describes how to use the Test Manager to troubleshoot a test run.

Starting a Test Run

When the harness is not running tests, it enables both the  button on the tool bar and the Run Tests > Start menu item.

Note – Only one test run at a time can be active in each Test Manager.

To start a test run using the current configuration, either click the  button or choose Run Tests > Start. You can also use the test tree pop-up menu to run a specific test or group of tests in a folder. See [Test Tree Pop-Up Menu](#).

Before the harness attempts to run the test suite, it verifies that the required configuration information is complete. You can view the configuration state in the Test Manager Properties browser. See [Viewing Test Manager Properties](#) for a description of the browser.

If the configuration information is not provided or is incomplete, the harness opens a dialog box advising you that the configuration must be completed before it can begin running tests. You can choose to open the configuration editor window or cancel the test run. If you choose to open the configuration, the harness opens the configuration at the incomplete section.

To change the test suite or work directory before running tests, refer to the following topics:

- [Opening a Test Suite](#)
- [Opening a Work Directory](#)

- [Creating a Work Directory](#)

If a JavaTest Harness agent is used to run the tests for your product, you must start the agent before you begin the test run. See *JavaTest Harness Agent User's Guide* for detailed information about the JavaTest Harness agent.

If the harness starts the test run and issues a request before the active agent starts running, the harness waits for an available agent until the timeout period ends. If the timeout period ends before an agent is available, the harness reports an error for the test.

Monitoring a Test Run

After the test run begins, the Test Manager displays information about the test run in the areas described in the following table.

TABLE 47 Monitor a Test Run

Area	Description
Test Tree	<p>The test tree uses colored icons to display the current run and test results status of the folders and tests in the work directory. As the harness completes running individual tests, it updates each test tree icon to indicate the test result status.</p> <p>See Monitoring With a Test Tree for detailed information about using the test tree to monitor the progress of the test run.</p>
Status Messages	<p>Below the test tree area is a resizable text area that displays information about current Test Manager activity. In this area the harness displays status messages about the state of the test run and the name of the test being run.</p>
Progress Indicator	<p>The Test Manager Status Line contains a progress indicator. The indicator displays the elapsed time of the previous test run when tests are not running. When tests are running, it automatically changes to the progress bar of the current test run. At the completion of the test run, the indicator changes to display the elapsed time.</p> <p>See Progress Indicator for information about using the test progress meter to monitor the progress of the test run.</p>
Progress Monitor	<p>A separate Progress Monitor is available that displays current, detailed information about the progress of the test run.</p> <p>See Progress Monitor for information about using the Progress Monitor.</p>
Information Area	<p>As tests run, the harness displays information about the run in the information area to the right of the test tree. The information area provides two views:</p> <p>Folder view - When you click a folder icon in the test tree, the harness displays a Summary tab, a Documentation tab, five status tabs, and a status field containing information from the work directory about a folder and its descendants. See Displaying Folder Information for detailed information about browsing folder information.</p> <p>Test view - When you click a test icon in the test tree or double click its name in the Folder view, the harness displays six tabbed panes that contain detailed information about the test. See Displaying Test Information for detailed information about browsing test information.</p>

While monitoring the test run in the Test manager, you can also display the contents of output logs being generated during the test run. See [Monitoring](#)

[Output Logs](#) and [Monitoring Services](#) for detailed information.

The harness also provides a web server that you can use to remotely monitor and control batch mode test runs. The HTTP Server provides two types of output:

- HTML Formatted Output allowing users to remotely monitor batch mode test runs in a web browser
- Plain Text Output intended for use by automated testing frameworks

See the *Command-Line Interface User's Guide* for details about running tests from the command line and using the web server.

Monitoring With a Test Tree

The test tree uses folder icons, test icons, and two independent types of filtering (run filtering and view filtering) to simultaneously display the following conditions:

- Progress of a test run

- Current test results in the work directory

When a test run begins, you can track its progress in the test tree by observing the folder and test icons. The test tree displays an arrow at the left of each folder and test icon as it is loaded and run.

After the harness completes running a test, it writes the test results to the work directory and updates the folder and test icons in the test tree. The test tree displays folder and test icons based on the view filter specified in the Test Manager window.

The harness supports using status colors specified by the user instead of the default color settings. See [Specifying Status Colors in the Command-Line Interface User's Guide](#).

Regardless of whether or not a test was run, the test tree displays filtered out



folder and test icons for those tests and folders filtered out by the view filter. All other icons are updated to reflect their current result status from the work directory.

Changing either the run or the view filter settings causes the harness to immediately update the folder and test icons displayed in the test tree.

See [View Filters](#) for a description of how to specify which test results from the work directory are displayed in the test tree.

See [Test Tree](#) for a detailed description of the icons, filters, and other features used in the test tree.

The goal of a test run, when using the appropriate view filter, is for the root test suite folder to display the passed folder icon. The passed root test suite folder icon signifies that all tests in the test suite not filtered out of the test run (by specifying tests that are run, exclude lists, keywords, and prior status) with passed test results. See [Changing QuickSet Values](#) for a description how to quickly set run filters that include or remove tests from a test run.

Click the test suite icon in the test tree to display status information for the test suite in the Test Manager information area. The view filter used in the test tree is also used to display folder status information. See [Displaying Folder Information](#) for a detailed description of the folder information displayed in this area.

By browsing the tabbed pane and the test tree, you can find the folders that contain tests without passed test results.

Using View Filters

In the toolbar at the top of the test tree is a list of view filters that you can use to select the status of the folders and tests displayed by the test tree. The harness includes a Current Configuration filter and an All Tests filter. Additional filters,

such as certification filters, can also be added by the test suite. Refer to your test suite documentation for detailed descriptions of any additional filters in the list of view filters.

Selecting a view filter only filters the status (folder colors and counters) displayed in the Test Manager window, not the tests that are run. You must use the configuration editor to filter the tests that are run. See [Specifying Tests to Run](#).

See [View Filters](#) for detailed information about the view filters available in the Test Manager.

Monitoring Output Logs

You can use the Log Viewer to monitor logs produced during a test run. To use the Log Viewer, your test suite must generate the logs that the viewer can display. See your test suite documentation for detailed information about the log files that it generates. See [Log Viewer](#) for a detailed description of the Log Viewer.

The Log Viewer enables you to perform the following actions when monitoring output logs:

- Display specific types of information from a log by selecting one or more notification levels.

For example, you can choose to display only the Critical and Warning messages.
- Monitor real-time content of output logs.

You can track log data in real time by selecting the Live Scrolling check box.
- Search log messages for text strings.

You can use the Find text field to search for literal strings within the currently viewed log data.
- Display multiple views of real-time content.

You can display data side-by-side by clicking the Open New Log Viewer button and using different criteria for displaying the output data in each viewer. Only the first instance of the Log Viewer is used to restore log viewing preferences next time the work directory is opened.
- Selection of log levels across all available logs in a single action.


Use the Selection Actions list to turn on a log level in all available logs. For example, you can turn on Error reporting for all logs. Because the operation only affects the current logs, logs created after you make the selection are not affected. To include logs created after the initial selection, reselect the action.
- Save log contents displayed in the log viewer. To save the log contents, click the Save button at the bottom of the viewer.

- Clear the contents displayed in the log viewer. To clear the log contents, click the Clear log button at the bottom of the viewer.

Agent Monitor Tool

If your test suite uses the harness agent, use the Agent Monitor tool to view all agents in a test system that are running tests. Choose Tool > Agent Monitor from the menu bar to open the tool window.

The Agent Monitor window contains two sections: Agent Pool and Agents Currently In Use.



If your test suite uses the harness agent, see the *JavaTest Harness Agent User's Guide* for a detailed description of using the Agent Monitor tool.

Stopping a Test Run

When the harness is running tests, it enables both the  button on the toolbar and the Stop menu item.

Either click the  button or choose Run Tests > Stop to stop a test run.

As it completes each test, the harness writes the test results (.jtr files) in the work directory. Stopping a test run causes the tests in progress to indicate an error.

When you stop a test run, the harness does not generate reports of test results. You must generate the reports from the Test Manager window or from the command line. See [Creating and Displaying Reports](#) for detailed information about test reports.

Troubleshooting a Test Run

Normally, the goal of a test run is for all tests in the test suite that are not filtered out by the current configuration to have passing results. See [Changing Configuration Values](#) for a description of how the current configuration filters tests in a test run.

If the root test suite folder contains tests with errors or failing results, you must troubleshoot and correct the cause to satisfactorily complete the test run.

Tests with errors  are tests that could not be executed by the JT harness. These errors usually occur because the test environment is not properly configured or the software under test is defective. See [Tests with Errors](#) for a detailed description of troubleshooting tests with errors.

Tests that failed  are tests that were executed but had failing results. See [Tests that Fail](#) for a detailed description of troubleshooting tests that failed.

The Test Manager window provides you with the following facilities to effectively troubleshoot a test run:

- Test Tree
- Folder View
- Test View
- Log Viewer

- Service Monitor

Test Tree

Use the test tree and view filters to identify specific folders and tests with errors or failing results. Open the red  and blue  folders until the specific tests that failed  or had errors  are displayed.

Folder View

When you click a folder icon in the test tree pane, the JT harness displays a filtered summary of its test status in the Test Manager information area that matches the test tree.

Note – The View filter chosen in the Test Manager window might change the summary values displayed in the folder view, but does not change the test results written in the work directory.

Click the Error and the Failed tabs to display the lists of all tests in and under a folder that were not successfully run. You can double-click a test in the lists to view its detailed test information. Refer to Test View below for a description of the test information that the JT harness displays.

Test View

When you click a test icon in the test tree or double-click its name in the folder view, the JT harness displays unfiltered, detailed information about the test in the information area. The Test Manager displays the current information for that test from the work directory.

Note – Because the Test Manager does not use a view filter when displaying test information, the test status displayed in the information area may not match the filtered view in the test tree or the folder Summary view.

The test view contains detailed test information panes and a brief status message at the bottom identifying the type of result. This message may be sufficient for you to identify the cause of an error or failure.

If you need additional information to identify the cause of the error or failure, use the following panes listed in order of their importance:

- [Test Run Messages](#) contains a Message list and a Message pane that display the messages produced during the test run
- [Test Run Details](#) contains a two-column table of name-value pairs recorded when the test was run.
- [Configuration](#) contains a two-column table of the name-value pairs derived from the configuration data that were actually used to run the test.

Log Viewer


Use the Log Viewer (select View > Logs) to monitor log files generated during a test run or to inspect log files after a test run is completed. See [Monitoring Output Logs](#) for a detailed description.

Service Monitor

If a test suite uses services, use the Service Monitor (select View > Services) to see the status of services. See [Monitoring Services](#) for a detailed description.

Browsing Test Information

You can quickly browse test information in the Test Manager window by clicking folder and test icons in the test tree.



This chapter is divided into the following topics:


- [Test Tree](#) - Describes the test tree and filtering used to display the test suite, its folders, tests and status icons.
- [Folder View](#) - Describes how to display filtered folder information in the Test Manager window.

- [Test View](#) - Describes how to display unfiltered test information in the Test Manager window.
- [Viewing Test Manager Properties](#) - Describes how to display the Test Manager Properties browser.
- [Viewing Test Suite Errors](#) - Describes how to display the Test Suite Errors dialog box.

Displaying Folder Information

The folder view contains filtered summary and status information about the tests in a test folder. This information is displayed both as values and as a pie chart. The folder view and test tree use the same view filter when displaying information.

To display the folder view, click a folder icon in the test tree. The folder view displays a Summary tab, a Documentation tab, five status tabs, and a status display.



During a test run, you can use the folder view to monitor the status of a folder and its tests. You can also use the folder view during troubleshooting to quickly locate and open individual tests that had errors or failed during the test run. When a status pane is empty, the harness disables its tab.

See [Summary Information](#) for a description of the information displayed in the Summary pane.

The Documentation tab displays test suite documentation, assuming the test suite developer has provided it. In the test tree, select a test (not a folder) to display its description, if any, in the Documentation tab.

See [Status Information](#) for a description of the folder information displayed by clicking the following status tabs:

- Passed (green with a check mark)
- Failed (red with an x)

-  Error (blue with an exclamation point)
-  Not Run (white with a dash)
-  Filtered Out (gray or shaded)

The status message displayed at the bottom of the pane provides information about the selected tab. The messages indicate that tests in the folder are loading or provide detailed status information about a selected test.

Summary Information

When you click a folder icon in the test tree, the harness uses the current view filter to display Summary information about the folder's test results.

The Summary pane contains header information that identifies the folder and the view filter presented in the Summary table and its associated pie chart. The pie chart displayed in the Summary pane is a graphical representation of the tabular data.

The following table describes the filtered work directory information that the Summary table and pie chart can display.

TABLE 48 Summary Pane Contents

Field	Description
Passed	The number of tests in a folder (including all of its subordinate folders) displayed in the test tree that were run and have passed test results.
Failed	The number of tests in a folder (including all of its subordinate folders) displayed in the test tree that were run and have failed test results.
Error	The number of tests in a folder (including all of its subordinate folders) displayed in the test tree that were run but had errors.
Not Run	The number of tests in a folder (including all of its subordinate folders) in the test tree that have not yet been run and were not filtered out.
Sub-Total	The total number of tests that were selected to run.
Filtered Out	The total number of tests in a folder (including all of its subordinate folders) displayed in the test tree that were filtered out. Tests that were filtered out include tests that you omitted from the test run by using keywords, prior status, or exclude lists.
Total	Total number of tests in a folder and its subordinate folders.

Note – The GUI only displays results of those tests in the work directory that match your *view* filter setting. Changing the view filter used in the Test Manager changes the values displayed in the Summary pane.

When using the All Tests view filter, new settings in the current configuration do not change the values displayed in the Summary pane.

When using the Current Configuration view filter, each time you make a change in the configuration, the values displayed in the Summary pane are recalculated and displayed based on the new settings in the current configuration. See the following example for a description of the use of the Current Configuration view filter and the All Tests view filter.

Example:

If you rerun a set of tests and use the Current Configuration view filter with Prior Status: Failed set in the configuration (see [Specifying Prior Status](#)), as actual test status in the work directory changes from Failed to either Passed or Error, the test status displayed in the Summary pane changes from Failed to Filtered Out.

If you change the view filter to All Tests, the test tree and Summary pane immediately display the actual results of all tests in the work directory, regardless of the Prior Status settings in the configuration.

See [Problems Viewing Test Results](#) for additional information about viewing test status in the test tree and Summary pane.

Click the appropriate status information tab to identify the individual tests in a category.

Status Information

In addition to Summary and Documentation information, the folder view contains five status tabs that use the view filter to group and list a folder's tests by their results in the work directory. See [Displaying Folder Information](#) for additional information.

- In the tabbed panes, click a test in the list to display the summary message at the bottom of the pane.
- By default the list has two columns, Name and Title. Click a heading to sort the list.
- To display alternate information in the second column, right-click on the column heading and make a selection from the Description or Runtime context menus.

Test Suite: sample-compiler			
Summary	Documentation	Passed	Failed
Please click the table header to sort the corresponding column data or use right click on the table header or the table body to show pop up menus allowing to change the column content or to perform actions on selected tests.			
Name	Description	Keywords	
lang/ARR/arr003/ar...	Runtime	Execution Status	
lang/CLSS/clss003...		Execution Start Time	
lang/CLSS/clss003/cl...	compiler n...	Execution End Time	
lang/CLSS/clss007/cl...	compiler n...		
lang/CONV/conv002/c...	compiler negative		
lang/EXPR/expr041/e...	compiler negative		
lang/EXPR/expr059/e...	compiler negative		
lang/EXPR/expr060/e...	compiler negative		

- Double click the test name or press Enter to display the test in the test tree and to view its unfiltered test information. See [Displaying Test Information](#) for additional information.

The colors of the following icons are the harness default settings. The harness enables you to use colors other than these default settings. See [Specifying Status Colors](#) in the *Command-Line Interface User's Guide*.

Passed

Uses the view filter to display the test names of all tests in the folder (including all of its subordinate folders) displayed in the test tree that had passing results when they were run.

Failed

Uses the view filter to display the path names of all tests in the folder (including all of its subordinate folders) displayed in the test tree that were run and had failing results.

Error

Uses the view filter to display the path names of all tests in the folder (including all of its subordinate folders) displayed in the test tree with errors that prevented them from being executed.

Not Run

Uses the view filter to display the path names of all tests in the folder (including all of its subordinate folders) displayed in the test tree that are selected by the view filter but have not been run.


Filtered Out

Uses the view filter to display a two-column list. The first column contains the names of tests in the selected folder whose results are filtered out by the selected view filter.

The second column contains a specific reason why the test result is filtered out by the view filter. The specific reason depends on the view filter criteria. See [View Filters](#) for a detailed description of filtering criteria.

Multi-Selection Panel

When multiple tests are selected in the test tree, the harness displays a Multi-Selection panel in the Information Area.



1. Test Tree Selection

2. Multi-Selection Panel


This panel contains a text description area at the top of the panel that describes the operations that can be performed using tests and folders selected in the test tree and listed below.

In the section below the text description area, the harness displays a list of the tests and folders selected in the test tree.

Displaying Test Information

The test view contains unfiltered, detailed information from the work directory about a specified test. To display the test view, click a test icon in the test tree or double-click a test name.

The test view contains six tabs and a colored status field (which indicates Pass or Fail).



Note – The test view does not use view filtering to display information. If you are using a view filter other than All Tests, the status color displayed in this view might not match the test icon or the folder view tab.

The following table describes the contents of the test view panes. The status field at the bottom of the pane contains a description of the test result and is visible in all of the test view panes.


TABLE 49 Information Pane Contents

Tab	Description
Test Description Pane	Displays the name-value pairs contained in the test description. The contents are input data and always available.
Documentation Pane	Displays test documentation, if it exists.
Files Pane	Contains a drop-down list of source files from the test description. Click a file name from the drop-down list to display its contents. The contents are input data and always available.
Configuration Pane	Displays a table of configuration name-value pairs used to run a specific test. The contents are output data and only enabled if the test was run.
Test Run Details Pane	Displays the name-value pairs that were recorded when the test was run. The contents are output data and only enabled if the test was run.
Test Run Messages Pane	Contains a tree and message panel of output from sections of the test. Click a name to display its contents. The contents are output data and only enabled if the test was run.

When an information pane is empty, the harness disables it.

Test Description Pane

Click the Test Description tab to display a two-column table of name-value pairs derived from the test descriptions cached in the work directory. Each test in a test suite has a test description.



The screenshot shows a software interface with a title bar 'Test: BigNum/addTest.html'. Below the title bar is a navigation bar with tabs: 'Test Description' (which is selected and highlighted in blue), 'Files', 'Configuration', 'Test Run Details', and 'Test Run Messages'. The main content area is titled 'Test Description Entries for the Selected Test'. It contains a table with two columns: 'Name' and 'Value'. The table has two rows: one for 'executeClass' with the value 'com.sun.demotests.bignum.AddTest', and another for 'sources' with the value 'AddTest.java'.

Name	Value
executeClass	com.sun.demotests.bignum.AddTest
sources	AddTest.java

When you open the test suite in the harness, the test finder reads the test descriptions and caches them in the work directory. Test descriptions in the cache and the Test Description pane are not updated until you close and reopen the test suite. Refer to your test suite documentation for detailed descriptions of the names and values displayed in the Test Description pane.

Name


The names displayed in the table identify the attributes and properties contained in the test description.

Value

The values displayed in the table are the attribute and property values that the harness used to run the test. The values are read from the files in the test suite.

Files Pane

The Files tab displays those files nominated by a test suite on a per-test basis. The Files tab can render .html, .rtf, and .txt files as well as most .au, .wav, .mid, .gif, .jpg, and .png files. You can browse but not edit source files in this panel.



The screenshot shows the 'Files' tab of a test configuration interface. The title bar says 'Test: BigNum/addTest.html'. The tabs are 'Test Description', 'Files' (which is selected), 'Configuration', 'Test Run Details', and 'Test Run Messages'. A dropdown menu shows 'File:BigNum/addTest.html'. Below the tabs is a table with two rows:

sources	AddTest.java
executeClass	com.sun.demotck.tests.bignum.AddTest

Choose a file from the drop-down list to display its contents.

Configuration Pane

The Configuration tab displays a two-column table of the name-value pairs that were derived from the configuration file and actually used to run the test.



The screenshot shows the 'Configuration' tab of a test configuration interface. The title bar says 'Test: BigNum/addTest.html'. The tabs are 'Test Description', 'Files', 'Configuration' (which is selected), 'Test Run Details', and 'Test Run Messages'. A table titled 'Configuration Values Used When the Selected Test Was Run' is displayed:

Name	Value
command.execute	com.sun.javatest.lib.ExecStdTestOtherJVMCmds:\$testSuiteRootDir./.demoapi.jar\$binaries/solaris-sparc/bin/java -classpath \$testSuiteRootDir/classes:\$testSuiteRootDir./.demoapi.jar\$testExecuteClass \$testExecuteArgs

The contents of this pane vary for each test suite. Because the table contains values that were used when the test was run, it may provide valuable information when troubleshooting a test run. Refer to your test suite documentation for detailed descriptions of the name-value pairs for your test.

Name

The names in the table identify test environment properties used by the harness to run the test.

Value

The values displayed in the table were used to run the test.

Test Run Details Pane

Click the Test Run Details tab to display a two-column table of name-value pairs that were recorded when the test was run and may provide valuable information when troubleshooting a test run. Refer to your test suite documentation for detailed descriptions of the result property name-value pairs for your test.

Detail properties about test run	
Name	Value
description	file:///snapshot/beta/b22/binaries/examples/snapshot/beta/b22/binaries/examples/javatest/simpleHTML/demo/cktests/BigNum/addTest.html
end	Thu Jul 13 11:44:35 PDT 2006
environment	test
execStatus	Passed. OK
javatestOS	SunOS 5.9 (sparc)
javatestVersion	4.0
script	com.sun.javatest.lib.StdTestScript
sections	script_messages execute
start	Thu Jul 13 11:44:31 PDT 2006
test	BigNum/addTest.html
timeoutSeconds	600
work	/home/clifflw/ws/demo/BigNum

Name

The harness derives property names from the test results file and displays them in the table with the following defaults:

- Information about the version of the harness used to run the test

- Information about the operating system used to run the test
- Date and time the test started
- Date and time the test ended
- Additional details recorded by the test script used to run the test

Because the properties listed in the table are a function of the test that you are running, the contents vary for each test suite.


Information written by commands, tests, and scripts as they are executing is displayed in the Test Run Messages pane.

Value

The values displayed in the table are from the test results file created by the harness after running the test.

Test Run Messages Pane

To display detailed messages describing what happened during the running of each section of the test, click the Test Run Messages tab. This information is useful when troubleshooting a test run.



The screenshot shows the 'Test Run Messages' tab selected in a browser window. The left pane, titled 'Summary', contains a tree view with nodes: 'Script Messages' (expanded), 'execute' (selected), 'messages', 'out1', 'out2', and 'Test Result'. The right pane, also titled 'Summary', displays the following information:

- The test was run by the following script class: `com.sun.javatest.lib.StdTestScript`
- The script logged the following messages:
[messages](#)
- Result Sections**
The following result sections were recorded:
[execute](#)
- Result**
Based on the results of the preceding sections, the script determined that the result of the test is:
 Passed. OK

At the bottom of the right pane, a green bar displays the text "Passed. OK".

The Test Run Messages tab contains the following areas:

- **Message List** - The vertical area on the left side of the Test Run Messages tab.
- **Message Area** - The vertical area on the right side of the Test Run Messages tab.
- **Test Result Status Bar** - The horizontal area at the bottom of the Test Run Messages tab.

Message List

The message list provides a detailed list of messages issued during a test run. Click an item in the list to display its contents in the message area. The message list contains links to the following types of messages:

- [Summary Message](#)
- [Output Summary and Result Messages](#)

- [Test Result Message](#)

Summary Message

Only one per test, this message summarizes all of the messages generated during a test run and provides hypertext links to their detailed contents. The Summary Message contains the following information in the message area:

- Test script used to run the test
- Messages logged by the test script
- Individual test result sections
- Test result and its result icon

Script Messages

This message is passed up from the script that executed the test. There is only one script message per test. Script messages vary for each test script. Refer to your test suite documentation for detailed descriptions of its script messages when troubleshooting a test run.

Output Summary and Result Messages

Each test result section has an Output Summary and Result message that provides summary messages and hypertext links to its detailed messages. The name of the Output Summary message is a function of the test suite and varies for each test suite.

Some tests have only one result section, while others have multiple sections. Refer to your test suite documentation for detailed descriptions of the tests when troubleshooting a test run.

The following table lists and describes the message types.

TABLE 50 Output Summary and Result Messages

Message Type	Description
Output Summary	<p>A two-column table listing the name and size of each output section. Each of the following output sections contains text generated while executing the test section:</p> <p>messages - Provides the command string used by the test script to run the test section. Unlike ref and log, the messages field always exists in a section.</p> <p>ref - The name of this message field is determined by the test and might be a name other than ref. A test can use this output stream to provide standard output information from the test section.</p> <p>log - The name of this message field is determined by the test and might be a name other than log. A test can use this output stream to provide standard error information from the test section. Many tests only use the log stream and include tracing as well as standard error information when writing to the log output.</p> <p>The contents of each output section varies from test suite to test suite. Refer to your test suite documentation for detailed descriptions of the test section messages when troubleshooting a test run.</p> <p>If no details exist in an output section, the harness does not create its hypertext link and indicates in the Size (chars) column that it is empty.</p>
Result	Contains a colored status icon and a brief description of the results of the specific test section. The color of the circle indicates the result of the test section.

Test Result Message

The Test Result Message indicates the cumulative result of the test. There is only one Test Result Message per test.

Note – For negative tests, the Test Result correctly indicates Passed when all of its test sections have failed.

Message Area

The area displays the messages issued during a test run. The number, names, and content vary for each test suite and may also vary for different tests in the same test suite.

Test Result Status Bar

The area displays an abbreviated form of the Test Result Message. See [Test Result Message](#) for detailed information.

Displaying Configuration Information

The harness provides special browsers for displaying configuration checklists, test environment values, exclude list contents, and configuration log information derived from the current configuration. This section contains the following topics:

- [Displaying the Configuration Checklist](#) - Describes how to display the checklist that a test suite's interview may produce.

The checklist is optional and may not be produced by all test suites.

- [Viewing Configuration Values](#) - Describes how to view the configuration values used to run a test suite.

When troubleshooting you can use the Test Environment browser to view the configuration values and their sources that were derived from the configuration file and used by test suite specific plugin code to execute and run tests.

- [Viewing Exclude List Contents](#) - Describes how to view the list of tests excluded from a test run.

You can use the Exclude List browser to display the list of tests that were excluded from a test run. The browser also displays details about individual tests selected in the list.

- [Displaying the Question Log](#) - Describes how to browse (in HTML format) the text of all completed questions asked in the configuration interview and their answers.

Displaying the Configuration Checklist


Your test suite might produce a checklist of steps that must be performed before running tests. The checklist is dynamically generated by the harness from the current configuration. Changes to the values in the current configuration can produce different checklist items.

If the tests suite produces a checklist, the harness enables the Show Checklist menu item. To view the Configuration Checklist of the current configuration interview choose View > Configuration > Show Checklist.

To close both the Configuration Checklist and the viewer, click the Close button at the bottom of the window.

Viewing Configuration Values

The Test Environment browser displays the configuration values used to run a test suite.



To open the Test Environment browser, choose View > Configure > Show Test Environment from the Test Manager menu bar.

The Test Environment browser contains a four-column table that displays information derived from the configuration file and used in configuring the test run. Useful features of the Test Environment browser include the following:

- Click and drag the column headers or their separators to rearrange the order and change the size of the columns.
- Click inside a table cell to display its contents in the text box below the table. This is a useful feature when the contents of a cell are too long for the table to effectively display them.

- Click a column header to alpha-numerically sort the contents of the table. This is a useful feature when searching for a specific name or value in a lengthy table.


The following table describes the contents of the Test Environment browser.

TABLE 51 Test Environment Dialog Box Contents

Name	Description
Entry Name	Identifies a name-value pair derived from the configuration file and used by test suite specific plug-in code to execute and run tests.
Value	A value specified by the user in the configuration file used to configure a test run.
Defined in file	Identifies the source of the configuration information used to run the tests. If your test suite uses a configuration (.jti) file to run tests, the source of the values is displayed.
Defined in environment	When appropriate, this field displays the environment name from the configuration.

Viewing Exclude List Contents

The Exclude List browser displays the list of tests excluded from the test run by the exclude list.



To open the Exclude List browser, choose **View > Configure > Show Exclude List** from the Test Manager menu bar.

The harness opens the Exclude List browser and displays the contents of the exclude list used to run tests and details about each test. You can use the browser to view but not edit the contents of the exclude list.

Use the Configuration Editor to add or remove exclude lists in a configuration. See [Configuring a Test Run](#) for detailed information.

Exclude List Contents

Information about individual tests in the exclude list is displayed in single, multi-column rows. Click a test in the list to display specific details in the text fields at the bottom of the panel.

Test Details

The following table describes the details displayed about individual tests highlighted in the Exclude List contents area.

TABLE 52 Exclude List Test Details

Field	Description
Synopsis	Provides annotated information about the excluded test
Keywords	Provides a list of keywords that describe why the test was excluded
Bug Ids	Lists the bug tracking IDs for the excluded test

Displaying the Question Log

The harness creates a log file of all the completed questions in the current, saved configuration file and their answers. The harness does not update the question log until you save the configuration file or click the **Done** button in the Configuration Editor.


Open the Question Log of the current, saved configuration file by choosing View > Configure > Show Question Log from the Test Manager menu bar.

The log provides a list of all questions in the saved configuration with links to the following details about each question:

- Question
- Question tag
- Question description
- Response (if appropriate)

Viewing Test Manager Properties

To view the properties of a test manager, choose View > Properties. The harness opens the Test Manager Properties viewer.



The Test Manager Properties viewer contains the following four areas:

- [Test Suite](#)
- [Work Directory](#)
- [Configuration](#)
- [Plug-Ins](#)

All value fields in the viewer can be highlighted and copied to the clipboard with keystroke Control-C.

Test Suite

The Test Suite properties area displays the Path, Name, and ID of the current test suite opened by the test manager.

Work Directory

The Work Directory properties area displays the path of the current work directory opened by the test manager.

Configuration

The Configuration properties area displays the Path, Name, Description, State, and Template of the current configuration interview opened by the test manager. The State field indicates whether the configuration is complete and tests can be run. It also identifies the availability of special filters.

Plug-Ins


The Plug-Ins properties area displays the name of the plug-ins used by the Test Manager. The plug-ins are provided by the test suite architect. The following table describes the properties that might be identified in the Plug-Ins properties area.

TABLE 53 Plug-Ins Area


Property	Description
Test Suite	The fully qualified name of the test suite class used by the test manager.
Test Finder	The fully qualified name of the test finder class used by the test manager.
Test Runner	The fully qualified name of the test runner class used by the test manager.
Interview	The fully qualified name of the interview class used by the test manager.

Viewing Test Suite Errors

When the harness detects errors in the test suite, it displays an error dialog box and enables the View > Test Suite Errors menu item.



To display the Test Suite Errors viewer, you can choose View > Test Suite Errors from the Test Manager menu bar.



The dialog box displays a list of errors detected in the test suite. Unless instructed otherwise, report any test suite errors to the owner of the test suite.

Creating and Displaying Reports

The harness does not automatically create reports at the end of a test run. You must use the harness to manually create a new report after the test run. You can create and view reports containing the following test run information:

- Tests grouped by test status
- Configuration interview questions and answers
- Test environment used for the test run

See [Creating Reports](#) for a description of how to create test reports.

To view reports in the harness Report Browser, choose Report > Open Report from the menu bar. See [Displaying Reports](#) for a description of how to view reports.

Because harness reports contain relative and fixed links to other files, you must update these links when moving reports to other directories. The harness provides a command-line utility for you to use when moving reports to other directories. See Moving Test Reports in the *Command-Line Interface User's Guide* for a description of how to use the `EditLinks` utility to move reports.

Creating Reports

The harness does not automatically create reports of test results after a test run. You must create test reports either from the harness GUI or from the command line in batch mode (see Writing Reports in the *Command-Line Interface User's Guide*).

- [Creating a Test Report](#)
- [HTML Options](#)
- [HTML Files](#)
- [KFL Options](#)

- [Creating a Known Failures List](#)

- [Report Files](#)


Reports might contain configuration values as well as test results. To ensure that any configuration values printed in reports are those that were used to run the tests, observe the following precautions after running tests for which you intend to generate one or more reports:

- Do not change any values in the current configuration.
 - Do not load a different configuration into the work directory.

Note – To minimize the chance of creating reports with configuration values that are inconsistent with the test results, either create reports after running the tests or use different work directories for different configurations.

▼ Creating a Test Report

1. Choose Report > Create Report from the Test Manager menu bar. The harness opens the Create a New Report dialog box.



2. Type the name of a report directory in the Report Directory field or click the Browse button to specify where to put the new reports.

You can either specify a new directory or an existing directory. If you ran reports earlier, the Report Directory field displays the directory from the previous run. If you use an existing report directory, the harness can save the previous reports as backups when it writes the new reports. Use the settings in the Backup Options pane to backup old reports and specify the number of backup reports to keep in the report directory.

3. The "Report Results for" drop down specifies the filter used to select the test results that are reported. You can choose Last Test Run, Current Configuration, All Tests, *Custom*, or Certification. If the *Custom* filter was previously renamed, the dialog box displays the current name of the custom filter. You can create or modify a custom filter for generating test reports for a specific set of test criteria.

See [Using View Filters](#) for a description of the filters.

See [Custom View Filter](#) for a description of how to create a custom view filter.

4. Check "Backup Options settings" to enable the report backup option and specify the number of backups preserved.

When "Backup old reports" is enabled, the harness saves the previous reports by appending a tilde and a sequential number to the .html extension (such as failed.html~1~). The harness maintains the specified number of copies by deleting the oldest copy when the limit of backups is reached for a specific report. Changing this or any other setting in the report dialog box does not alter any previously saved backup reports. Existing backups are not deleted if backups are turned off and file names are not changed as old backups are deleted.

The harness backs up the entire set of reports. If the first set of reports included HTML, Text, XML, and COF formats, and the next set of reports are generated in XML format only, the harness creates backups of the previous reports (appending the appropriate tilde and sequence number to the backup file name). The harness generates the new top-level index.html file and updates its hyperlinks to maintain a self-consistent backup report set.

5. In the left column, choose the report format(s) to be generated by the harness. The options set in this dialog are persistent. Once set, they are used each time a report is generated. These settings also apply to reports printed from the command-line interface.

HTML Report: An HTML report showing configuration information, a result summary, and environment values. See [HTML Options](#) and [KFL Options](#).

Plain Text Report: A text report showing only the test names and their result status.

XML Report: An XML report containing configuration information, a result summary, and all result data for each test. This report is versatile - it can be used as input to Merge Reports and can be converted to other report formats. However, the file can be larger and slower to generate than other formats.


COF Report: The report browser displays a cof.xml hyperlink to the COF report page, which contains a report in the COF format. COF is an extensive XML format containing environment, configuration and test result data.

6. Click the Create Report(s) button.

The harness writes the reports and displays a dialog box that gives you the option of either viewing the new reports in the report browser or returning to the Test Manager window.

HTML Options

If you selected HTML Report in the Report Formats list, use the HTML Options tab to select the sections of the main HTML report file that are generated.



The following options are available for generating HTML reports:

- **Configuration** - Selecting this option enables all of the following subordinate options:
- **Question Log** - Generates a report that is the equivalent of the Configuration Question Log.
- **Test Environment** - Generates a report that is the equivalent of the Show Environment dialog box.
- **Standard Values** - Generates a report that contains the values from the Quick Set Mode.
- **Results Summary** - Generates a report of the pass, Fail, Error, Not Run, and Total values.

The HTML report provides hyperlinks to content in the other HTML files. If it is not selected, the hyperlinks are not generated.

- **Known Failures** - Generate a report of known failures, based on one or more [Known Failures List](#) (KFL) files. When the value for "Specify a Known Failures List?" is set to Yes in the configuration editor, and one or more KFL files have been specified, the settings are stored in your user preferences and used as the default when the KFL option is selected.

- **Keyword Summary** - Generates a report that provides a count of the number of occurrences of keywords that appeared in the selected tests.

HTML Files

Use the options on this tab to specify the content and the location of HTML reports. The main report is the home page for browsing HTML reports. It can be named `report.html` or `index.html`. The main report contains hyperlinks to the extra files you choose to generate. The extra files you can choose are as follows:

- Passed Tests (`passed.html`): Tests that were executed during the test run and passed.
- Failed Tests (`failed.html`): Tests that were executed during the test run but failed.
- Error Tests (`error.html`): Tests that had errors and could not be run.
- Not Run Tests (`notrun.html`): Tests that were not excluded from the test run but were not run.

The main report and any extra files are written to the location you specified in the Report Directory field.

KFL Options in HTML Reports

Known failure list reports enrich the reporting output so you can monitor the status of certain tests across test runs. This section describes how to create and use a known failures list and discusses KFL reports and the [Known Failure Analysis](#).

Using a Known Failures List

A known failures list (KFL) is list of tests or test cases that are known to fail. Its purpose is to provide failure data for reporting, so that failure behavior can be tracked over time. Using a known failures list is optional and the feature is off by default. To activate the feature, answer yes to the Specify a Known Failures List? question in the configuration editor.

Once KFL files have been specified, (see [Creating a Known Failures List](#) and [Specifying a Known Failures List](#)) you can choose the Known Failures option in the HTML Options tab. This enables Known Failure Analysis options on the KFL

Options tab. Options you check on this tab are preserved as preferences for future reports. This is true if reports are launched from the user interface or the command line.

Reporting Options:

- Check for test discrepancies. This feature is No by default. To activate this option, choose it in the user interface.

Optional files/sections to generate:

These options are set to Yes by default.

- List tests which are expected to fail and are still failing. See [Unexpected Error \(kf1_fail2fail.html\)](#).
- List tests which were expect to fail but resulted in error instead. See [New Passed \(kf1_fail2error.html\)](#).
- Report on tests in KFL which are now missing.

Any generated data is added to the [Known Failure Analysis](#) which is found towards the end of the HTML report (report.html and/or index.html). It is a summary of various comparisons between the selected result set (Current Configuration, Last Test Run, etcetera) and the items listed in the KFLs provided in the configuration.

Creating a Known Failures List

The KFL is a text file with the extension .kf1.

Note – The KFL file name or its path must not begin with a dash “-” or contain spaces. As described in [Specifying Known Failures Lists With kf1](#) in the *Command-Line Interface User’s Guide*, a space is a separator on the command line, therefore file path arguments such as C:\Program Files\myconfig\foobar do not work.

The .kf1 file lists one test or test case per line. You have the option of specifying a bug ID following the test name (a space separator is required). Use # for comments. For example:

```
# Demo.kf1
lists/DoublyLinkedList/insertTest.html 0000123
BigNum/subtractTest.html 0000456
BigNum/compareTest.html 0000789
```

If you provide a bug prefix URL, that ID will be appended to that address, creating a convenient link in your report. To specify the bug prefix URL, select File > Preferences. Under Test Manager, select [Reporting](#), and specify the URL.

Note – This feature does not validate the URL or perform any processing.

Note –

Specifying a Known Failures List

Follow these steps to use one or more known failure lists to add failure analysis data to HTML reports.

1. From the configuration editor, select Configure > Edit Configuration.
2. Under Parameters, select "Specify a Known Failures List?" and choose Yes. Once Yes is chosen the parameter "Specify Known Failures List Files" is active.
3. Choose one or more KFL files, as described in the configuration editor's [KnownFailuresListInterview](#).
4. The files you choose are stored in your user preferences and are considered the defaults.

If you have specified KFL files in the configuration editor it's preferable to modify the list using the configuration editor. If you want to modify the list of KFL files from the command line, see [Specifying Known Failures Lists with kf1](#) in the *Command Line Interface User's Guide*.

Known Failures List Reports

If you specified a known failures list in the configuration editor, the HTML report will include a section titled Known Failure Analysis. When you create a report you can check the HTML Option "Known Failures" to create the [New Passed](#), [Missing \(not run\)](#), and [New Failures](#) reports. The options on the KFL Options tab generate reports for [New Passed](#), [Missing \(test not found\)](#) and [Old Failure](#).

Known Failure Analysis

The Known Failure Analysis table in the HTML report attempts to describe the differences found in the set of results being analyzed versus what you provided in the KFL. The KFL is the set of expected failures of tests and test cases; if they did not fail in the current set of results, that is considered a discrepancy. This is a sample table:

Known Failure Analysis

Known Failure File(s):

- </Users/work/etc/myfile.kfl>

KFL Discrepancies	Tests (38)	Test Cases (4)
New Passed	1	3
Unexpected Error	0	0
Missing (not run)	3	1
Missing (test not found)	1	0
New Failure	33	0
Old Failure	2	(not calculated)

The headers **Tests (#)** and **Test Cases (#)** contain a number representing the number of discrepancies found in that column. The numbers below that header should add up to that number (except the Old Failure does not count as a discrepancy).

The Known Failure Analysis table contains numbers linked to each of the report categories below. If the number is clicked, the user is taken to a file which has details - basically the information you'd find in the KFL file. The test name or test case name and the associated bug IDs. The test names are hyperlinked to the JTR result file in the work directory and the bug ids are hyperlinked if the bug URL preference is set in the Test Manager Preferences (as described in [Reporting](#)).

New Passed

A test or test case in the current set of results has a Passed status, when it was expected to fail.

Sample scenario:

1. A product under development has a defect described in bug 1234, which exists in builds 1-5. The quality department now expects an error in test abc123 whenever the tests are run against the product, and has put test abc123 on the known failures list (KFL).
2. Build 6 arrives and test abc123 now passes because the defect has been fixed.
3. By looking at this Fail to Pass section of the report, the quality department will see test abc123 listed and investigate the reason this test is suddenly passing.
4. After confirming the fix, a typical action would be to remove test abc123 from the KFL.

Unexpected Error

A test or test case in the current set of results has an Error state, but it was expected to Fail. An Error usually indicates some sort of problem executing the test. Investigate items in this category to see why they resulted in an Error rather than a simple Pass or Fail.

Missing (Not run)

For some reason the test on the KFL was not run in the set of results being reported. It may not indicate a problem if a partial set of results is being analyzed, or if the KFL contains a wide set of tests, all of which would never appear in a single set of results.

Missing (test not found)

The results for a test listed in the KFL are missing. Because the test was listed in the KFL, it was expected to exist and Fail. A missing test may not indicate a problem, but should be investigated. This section can be disabled by deselecting the appropriate option in the HTML KFL report options in the Create Report dialog.

New Failure

Any test or test case which has a Failed status in the current results but does not appear in the KFL.

Old Failure

The lists of tests and test cases which failed and were expected to fail. This is not a discrepancy and is provided for informational purposes.

Report Files

The possible contents of the report directory are as follows:

```
index.html
/html
    config.html
    env.html
    error.html
    excluded.html
    failed.html
    kfl_fail2error.html
    kfl_fail2fail.html
    kfl_fail2missing.html
    kfl_fail2notrun.html
    kfl_fail2pass.html
    kfl_newfailures.html
    kfl_tc_fail2error.html
    kfl_tc_fail2missing.html
    kfl_tc_fail2notrun.html
    kfl_tc_fail2pass.html
    kfl_tc_newfailures.html
    notRun.html
    passed.html
    report.css
    report.html
/text
    summary.txt
```

```
/xml  
  report.xml
```

In the `html` directory, the KFL report file names correspond to the KFL reports as follows:

TABLE 54 accessing Online Information from the GUI

HTML Report	File Names
New Passed	<code>kfl_fail2error.html</code> , <code>kfl_tc_fail2error.html</code>
Unexpected Error	<code>kfl_fail2fail.html</code> , <code>kfl_tc_fail2fail.html</code>
Missing (Not run)	<code>kfl_fail2failmissing.html</code> , <code>kfl_tc_fail2failmissing.html</code>
Missing (test not found)	<code>kfl_fail2notrun.html</code> , <code>kfl_tc_fail2notrun.html</code>
New Failure	<code>kfl_fail2pass.html</code> , <code>kfl_tc_fail2pass.html</code>
Old Failure	<code>kfl_fail2newfailures.html</code> , <code>kfl_tc_fail2newfailures.html</code>

Displaying Reports

You can use the Report browser or a web browser to display harness reports.

▼ Display Reports in the Report Browser

1. Choose Report > Open Report from the menu bar.

The harness opens a file chooser dialog box for you to specify a report directory. When you specify a report directory, the harness opens the Report Browser.

Report Browser X

File Help

File: index.html < > ⌂

DemoTCK 1.0 Test Suite (HTML Tests)

Date of report: 19 May 2011 15:35:52

[HTML Report](#)
Standard JavaTest Harness HTML report. Can show a summary of the results, configuration information, and environment values.


[Plain Text Report](#)
Standard JavaTest Harness text report showing only test names and their result status string. Suitable for parsing by external program.

[XML Report](#)
Standard JavaTest Harness XML report format. Contains configuration information, result summary, and all result data for each test. This report is versatile - it can be used as input to Merge Reports and can be converted to other report formats. However, compared to other formats, the file can be larger and slower to generate.

[COF Report](#)
Standard JavaTest Harness COF report format based on XML. Contains result summary, and all result data for each test.

2. Choose the report format from the directory listing.
 - If you choose the text format version of the report, the browser displays a [summary.txt](#) hyperlink to the summary page. The summary page provides a text list of tests that were run and their test result status.

- If you choose the XML format version of the report, the browser displays a `report.xml` hyperlink to the XML report page. The XML Report page provides a report of the configuration values used to run the tests, the tests that were run, and their test result status.
- If you choose the HTML format version of the reports, a second directory listing is displayed. On the toolbar, you can use the report browser's back button (<) to return to the initial report page. You can also click the file name showing on the toolbar to open a dropdown of recently visited files and directories.



3. To see a list of the HTML reports click the Report directory hypertext link.

Report Browser

File Help

File: html\report.html

Configuration and Other Settings

Test suite	D:\javatest\test\tag\examples\javatest\simpleHTML\demotck
------------	---

Standard Values

Tests	(Entire Test Suite)
Prior Status	(Any Status - Pass, Fail, Error, Not Run)
Excluded Tests	(No entries or no exclude list specified)
concurrency	4
Timeout factor	2
Keywords	(No keywords specified)

How to run the tests

Configuration Log	DLPHTMLTestConfig
Environment	DLPHTMLTestConfig

Where to put the results:


Work directory	D:\javatest\work
Report directory	D:\javatest\work\Reports\html

Results

Tests that passed	16
Tests that failed	1
Total	17

Known Failure Analysis

4. Use the hyperlinks within report.html to display the detailed report files in the report browser.



5.

Report Browser Contents

The following table describes the contents of the Report Browser.

TABLE 55 Report Browser Contents

Component	Description
Menu bar	<p>The menu bar contains a File and a Help menu.</p> <p>Use the File menu to generate new reports, open existing reports, and to close the Report Browser.</p> <p>Use the Help menu to display Report Browser online help.</p>
tool bar	<p>The tool bar contains a File field and three navigation buttons.</p> <p>The File field displays the name of the current report and provides a drop-down list of reports previously opened in the browser. As reports are opened, the harness adds their names to the drop-down list enabling you to navigate to any previously displayed report.</p> <p> Returns to the previously displayed report page.</p> <p> Opens the next report page that was displayed.</p> <p> Returns to the <code>report.html</code> file. The <code>report.html</code> file is the root page and links to all of the other test report pages.</p>
Contents area	<p>The Report Browser displays the report file contents in the area below the tool bar. The Report Browser displays text files as well as HTML files. For HTML files, you can use hyperlinks in the report to display additional related reports.</p>

See [Keyboard access](#) for a description of how the keyboard can be used to navigate the Report Browser.

HTML Report Files

The following table lists and describes the HTML report files.

TABLE 56 View Reports Offline

Report Files	Description
config.html	Contains the configuration interview questions and your answers used for the test run.
env.html	Contains the name-value pairs derived from the configuration file that were used for the test run.
error.html	Contains a list of the tests that had errors and could not be run.
excluded.html	Contains a list of the tests that were excluded from the test run.
failed.html	Contains a list of the tests that were executed during the test run but failed.
notRun.html	Contains a list of all tests that were not excluded from the test run but were not run.
passed.html	Contains a list of the tests that were executed during the test run and passed.
report.html	Contains links to all of the HTML files and additional information.

Viewing Reports Offline

You can view the reports offline by opening the `html` files in a web browser or opening the `summary.txt` report in any text editor.

The `report.html` file is the root file that links to the other HTML reports. The `summary.txt` report contains a list of all tests that were run, their test results, and their status messages.


Merging and Converting XML Test Reports

You can use the Report Converter tool to merge harness generated XML test reports from different work directories into a single report. XML files not generated by the harness are not supported by using the XML Report type in the Test Manager report system.

▼ Merge XML Reports

1. Choose either Tools > Report Converter or Settings > New from the menu bar to launch the Report Converter wizard.

The harness opens the Report Converter wizard.



See [Report Converter Wizard](#) for a detailed description of the wizard.

2. In the XML Input Files panel, specify the directory where the Report Converter Tool writes the merged XML report file.


3. Specify the harness generated XML reports used as sources for generating the merged XML report file.

You can choose a single source file in the wizard if you are using the Report Converter tool to convert a harness generated XML test report to an output type provided by your test suite.

If you are merging multiple XML test reports, click the Add More button to open additional source file fields.

4. Click the Next button.

The harness displays the Report Options panel.



5. In the Report Options panel, specify how conflicts between merged reports are handled.


The default setting is to always handle identical results in the two reports as a conflict.

The option of resolving conflicts using the most recent result is not selected. When the report is created, the tool displays a Resolve Conflict dialog box for each conflict that is detected. Choosing the option of having the tool automatically resolve the conflicts enables the tool to create the report without displaying the Resolve Conflict dialog box.

1. Choose the report output format.
2. Click the Create Report(s) button to create the report.

3. Resolve any conflicts identified by the tool.

If conflicts exist in the reports and the option to resolve conflicts by using the most recent result was not enabled, the tool displays a Resolve Conflict dialog box for each conflict that is detected.



- If you only click the Resolve using most recent checkbox and click the Resolve button, the tool resolves the conflict for the specified test and displays the next conflict detected.
- If you select a report in the list, the tool enables the Resolve remaining conflicts using selected report checkbox. If you only click the Resolve remaining conflicts using selected report checkbox and click the Resolve button, the tool resolves all conflicts in the generated tests.

Resolve Conflict



Test name: lists/LinkedList/appendTest.html

Select report to be used in merged report:

E:\ws\jt40\newReportDemo\report.xml PASSED

E:\ws\jt40\newReportDemo\report.xml PASSED

Resolve remaining conflicts using selected report

Resolve using most recent

Resolve

Cancel

Auditing Test Results

The harness includes an audit tool that you can use to analyze the test results in a work directory. The audit tool verifies that all tests in a test suite ran correctly and identifies any audit categories in a test run with errors.


You can use the GUI or the command-line interface to audit a test run. See the *Command-Line Interface User's Guide* for a detailed description of auditing a test run from the command line.

▼ Audit a Test Run

1. Choose Tool > Test Results Auditor from the menu bar.

The harness launches the Test Results Auditor and the Options dialog box. If you are repeating an audit, you might have to open the Options dialog box from the menu bar.

2. If the harness did not launch the Options dialog box, choose Audit > Options from the menu bar.
3. In the Options dialog box, specify the reference test suite.



4.

See [Audit Test Results Options](#) for a detailed description. You can use the drop-down list or the chooser to specify a test suite. If you choose a reference test suite, the harness sets the entries in the work directory drop-down list to the work directories that are currently loaded and matches the specified test suite. If you have multiple test suites and work directories, specifying a test suite can simplify choosing the options.

The harness always uses the test suite associated with the work directory that you choose to audit. See Work Directory below for a description of how to choose a work directory to audit.

5. In the Options dialog box, specify the work directory.

The harness audits the work directory named in the Work Directory field. A blank field indicates the work directory is not set.

You can use the drop-down list or the chooser to specify the work directory to audit. If you choose a reference test suite, the harness only lists the work directories associated with it in the drop-down list. You are not limited to using these work directories. If you choose a work directory, the harness uses the test suite associated with the work directory and sets the entries in the Configuration File drop-down list to those most recently used with the work directory.


If you do not choose a work directory, the harness uses the work directory associated with the configuration file that you specify. See Configuration File below for a description of how to choose a reference configuration file.

6. In the Options dialog box, specify the configuration file.

You can use the drop-down list or the chooser to specify a reference configuration file. If you specify a configuration file, it must be associated with the work directory. If the configuration file is not associated with the work directory, the harness displays an error message without performing the audit.

1. Click the Start Audit button at the bottom of the Options dialog box.

When the harness completes the audit, it displays the results in the Test Results Auditor.



See [Test Results Auditor](#) for detailed description of the Test Results Auditor.

To repeat the audit, choose Audit > Options from the menu bar to open the Options dialog box and click the Start Audit button.

2. Choose File > Close from the menu bar to close the Test Results Auditor.

Troubleshooting With the GUI

The harness provides information you can use in troubleshooting problems. To troubleshoot problems using the harness see the following topics:

- [Harness Fails During Use](#)
- [Problems Running Tests](#)
- [Problems Viewing Test Results](#)
- [Output Overflow Message Displayed in Test Run Messages](#)
- [Problems Viewing Reports](#)
- [Problems Writing Reports](#)
- [Problems Moving Reports](#)

Harness Fails During Use

If the harness fails, you can use the `harness.trace` file in your work directory to help troubleshoot the problem. The `harness.trace` file is a plain-text file that contains a log of harness activities during the test run. It is written in the work directory, is incrementally updated, and is intended primarily as a log of harness activity.

Problems Running Tests

The goal of a test run is for all tests in the test suite that are not filtered out to have passing results.

If the root test suite folder contains tests with errors or failing results, you must troubleshoot and correct the cause to satisfactorily complete the test run. See [Troubleshooting a Test Run](#) for information about the resources that the harness provides for troubleshooting.

Tests with Errors

Tests with errors are tests that could not be executed by the harness. These errors usually occur because the test environment is not properly configured. Use the Test tabbed panes and the Configuration Editor to help determine the change required in the configuration.

The following is an example of how the Test Manager tabbed panes and the Configuration Editor can be used to identify and correct a configuration error:

1. Use the test tree to identify the folder containing test that had errors.
2. Click the folder icon to open its Summary tab in the Test Manager window.
3. Click the Error tab to display the list of tests in the folder that had errors.
4. Double-click a test in the list to display it in the test tree and view its detailed test information.
5. Click the Test Run Messages tab to display detailed messages describing what happened during the running of each section of the test.

The contents of each output section vary from test suite to test suite. Refer to your test suite documentation for detailed descriptions of the test section messages when troubleshooting a test run.

1. Click the Configuration tab to display a two-column table of the name-value pairs that were derived from the configuration file and actually used to run the test.

The names in the table identify test environment properties used by the harness to run the test. The values displayed were used to run the test. Refer to your test suite documentation for detailed descriptions of the name-value pairs for your test.

2. Choose View > Configuration > Show Question Log to view the Question Log of the current, saved configuration.

Use the question log to identify the configuration value that is incorrect and its configuration question.

1. Search the configuration file for the specific characters or character strings that must be changed.

See [Searching a Configuration](#) for a detailed description of how the current configuration can be searched for a character or string of characters.

1. Click the Done button to save your changes to the configuration file

Rerun the tests.

Tests that Fail

Tests that fail are tests that were executed but had failing results. The test or the implementation might have errors.

The following is an example of how the Test Manager tabbed panes can be used to identify and correct a test failure:

1. Use the test tree to identify the folder containing test that had errors.
2. Click the folder icon to open its Summary tab in the Test Manager window.
3. Click the Error tab to display the list of tests in the folder that had errors.
4. Double-click a test in the list to display it in the test tree and view its detailed test information.
5. Click the Test Run Messages tab to display detailed messages describing what happened during the running of each section of the test.

The contents of each output section vary from test suite to test suite. Refer to your test suite documentation for detailed descriptions of the test section messages when troubleshooting a test run.

Problems Viewing Test Results

Most problems in viewing test results in the Test Manager result from the use of view filters (other than the All Tests view filter) with a current configuration set to run specific tests (such as, running tests based on their prior status). When a view

filter other than All Tests is used in the Test Manager, only the fields of the filtered category appear to be updated in the Test Manager Summary tab. This is normal behavior of the GUI when view filters are used.

The harness *only* displays tests in the GUI that match the specified view filter criteria. All other tests are displayed as Filtered Out.

As test results change, the harness moves the tests to the Filtered Out category (not to a test result category) in the Test Manager and turns the appropriate node in the test tree gray. Consequently, the fields for the other categories in the Test Manager Summary tab might not appear to be updated.

Example:

If you change the current configuration to run only tests with a prior status of Failed and use the Current Configuration view filter, the Test Manager displays all tests that are not a Failed status as Filtered Out. This enables you to monitor only those tests with a previous Failed status. When you begin the test run, any tests with Passed or Error results are displayed in the Filtered Out category of the Test Manager. To view the actual test results, change to a different view filter. See [View Filters](#) for additional information. of the view filters.

Output Overflow Message Displayed in Test Run Messages

An output stream in the Test Run Messages Pane might display the following message:

Output overflow:the harness has limited the test output of the text to that at the beginning and the end, so that you can see how the test began, and how it completed.

If you need to see more of the output from the test, set the system property `javatest.maxOutputSize` to a higher value. The current value is 100000

Set the system property of `javatest.maxOutputSize` by using the syntax in:

```
java -Djavatest.maxOutputSize=200000 -jar lib/javatest.jar  
....
```

If you see this message, restart the harness with the harness VM system property `javatest.maxOutputSize` value set to a greater number and rerun the test to ensure that all of the data is saved.

The value of `javatest.maxOutputSize` is an integer subject to the maximum integer size of the VM. It sets the number of characters allowed in the output.

Problems Viewing Reports

The harness does not automatically generate reports of test results after a test run. You must generate test reports either from the command line or from the harness GUI. See [Creating Reports](#) for detailed information.

Problems Writing Reports

Filters are used to write test reports for a specific set of test criteria. Verify that you are using the appropriate filter to generate reports of test results. See [Creating Reports](#) for detailed information.

Problems Moving Reports

Test reports contain relative and fixed links to other files that might be broken when you move reports to other directories.

You must update these links when moving reports to other directories. The harness provides an `EditLinks` utility that updates the links in the reports for you when moving reports. See the *Command-Line Interface User's Guide*.

Glossary

- .jte** FilesSee [environment files](#).
- .jti** FilesSee [configuration file](#).
- .jtp** FilesSee [parameter files](#).
- .jtr** FileSee [test result files](#).
- .jtx** FilesSee [exclude list](#).
- .kfl** FilesSee [Known Failures List File](#).

A

All Tests View FilterA test tree [view filter](#) that displays all folders and tests in the [test suite](#).

AuditThe JT harness includes an audit tool that you can use to analyze the test results in a work directory. The audit tool verifies that all tests in a test suite ran correctly and identifies any audit categories of a test run that had errors. You can use the GUI or the command-line interface to audit a test run.

B

C

ClassThe prototype for an object in an object-oriented language. A class might also be considered a set of objects that share a common structure and behavior. The structure of a class is determined by the class variables that represent the state of an object of that class and the behavior is given by a set of methods associated with the class.

ConfigurationInformation about the computing environment required to execute a test suite.

In the GUI, you can use the Configuration Editor to collect or modify configuration information or to load an existing configuration. See [Configuration Editor](#). The Configuration Editor collects the following two types of data in a [configuration file](#):

- [Test environment](#)
- [Standard Values](#)

In the command-line interface, you can perform the following tasks:

- Use the [EditJTI](#) utility to modify configuration information (see [EditJTI](#)).
- Set specific configuration values in the command line when starting the harness.

Configuration EditorThe Configuration Editor provides two editing modes, the Question mode and the Quick Set mode. Use the Question mode to create a configuration file for the test run and to search interview titles, questions, and answers for character strings. Use the Quick Set mode to modify specific runtime values.

To open the Configuration Editor, choose Configure -> Edit Configuration from the Test Manager menu bar.

Configuration FileContains all of the information collected by the [configuration editor](#) about the test platform.

The harness derives the [configuration values](#) required to execute the test suite from [environment entries](#) in a [configuration file](#) (.jti).

Use the [Configuration Editor](#) or [EditJTI](#) to change configuration values in a .jti file.

You can also set specific values in the command line.

Configuration ValueA value specified by the user for the purpose of configuring a test run.

Configuration values are derived from [environment entries](#) in a [configuration file](#) (.jti) and used by test suite specific plugin code to execute and run tests.

Use the [Configuration Editor](#) or [EditJTI](#) to change the configuration values in the .jti file. You can also set specific configuration values in the command line.

For legacy test suites the configuration value is read from an [environment file](#) (.jte). Current test suites do not use or support the environment file.

Current

ConfigurationThe configuration containing the test environment and standard values currently loaded in the test manager or specified in the command line for use in running tests and displaying test status.

Current Configuration

FilterA [filter](#) that only displays or generates reports for the folders and tests that have not been [filtered out](#) in the configuration.

D

DesktopThe configuration and layout of the windows used by the JT harness.

The desktop is saved when you exit from the harness and is automatically restored in your next session.

The JT harness desktop is displayed using [tabs](#).

E

EnvironmentSee [Test Environment](#).

Environment EntryA name-value pair derived from a configuration file and used by test suite specific plugin code to execute and run tests. These name-value pairs provide information ([configuration values](#)) about how to run tests of a test suite on a particular platform.

For legacy test suites, the name-value pairs are read from an [environment file](#) (.jte) and derived from the [configuration file](#) (.jti). Current test suites do not use or support the environment file.

Environment FilesContain one or more test environments used by legacy test suites.

Environment files are identified by the .jte extension in the file name.

Current test suites do not use or support the environment file.

ErrorThe test is not filtered out and the JT harness could not execute it. There are no test results for tests having errors. Errors usually occur because the test environment is not properly configured.

In the GUI, the JT harness displays error icons for tests with errors and for folders containing any tests with errors. Folders marked with error icons can also contain tests and folders that are Failed, Not Run, Passed, and Filtered out.

Exclude ListExclude list files (*.jtx), supply a list of invalid tests to be filtered out of a test run by the test harness. The exclude list provides a level playing field for all implementors by ensuring that when a test is determined to be invalid, then

no implementation is required to pass it. Exclude lists are maintained by the technology specification Maintenance Lead and are made available to all technology licensees.

In the GUI, use the configuration editor to add or remove exclude lists from a test run. In the command line, you can specify an exclude list in the command.

To view the contents of an exclude list, choose **Configure -> Show Exclude List** from the Test Manager menu bar. Exclude lists can only be edited or modified by the test suite Maintenance Lead.

F

FailTest results determined by the JT harness that do not meet passing criteria.

In the GUI, the JT harness displays Failed icons for tests that the test suite has determined have failing results and for folders containing any tests with fail results. Folders marked with Failed icons can also contain tests and folders that are Not Run, Passed, and Filtered out.

Filtered OutFolders and their tests that are excluded from the test run by one or more [test run filters](#).

In the GUI, Filtered Out folders and tests are identified in the test tree by grey



folder and test icons.

FiltersA facility in the JT harness that accepts or rejects tests based on a set of criteria. There are two types of filters in the JT harness, view filters and run filters. View filters are set in the [Test Manager](#) to display the results for specific folders and tests and to create test reports. Run filters are set in the [Configuration Editor](#) or are specified as commands in the command-line to specify which tests are run.

G

GlossaryUse the Glossary tab in the left pane of the help viewer to open the glossary.

The glossary pane is divided into two areas. The top area displays the list of terms and the bottom area displays their definition.

Glossary entries are listed in alphabetical order. You can scroll through the list or search for a specific term.

To search for a specific term, enter it in the Find field and press Return. If the term is in the glossary, the harness highlights it in the list and displays its definition. Press Return to repeat the search.

H

I

InterviewFor the JT harness to execute a test suite, it requires information about how your computing environment is configured. The Configuration Editor uses an interview to simplify the process of collecting this information.

Because the quantity and scope of this information depends on the test suite, a test suite might include a specific interview for the Configuration Editor to use.

The information collected by the interview is written to a configuration file (.jti) and used by the JT harness to derive the [environment variables](#) required to execute the test suite.

Interview FileSee [configuration file](#).

J

JavaTest Harness

PreferencesA dialog box that you can use to set the window style and tool tip options used by the JT harness. To open the Preferences dialog box, choose File -> Preferences from the Test Manager menu bar.

JTIStandard file extension for a configuration file. See [configuration file](#).

K

KeywordsSpecial values in a [test description](#) that describe how the test is executed.

Keywords are provided by the test suite for use in the Configuration Editor or command line as a filter to exclude or include tests in a test run.

Known Failures List

FilesKnown Failures List (KFL) files (*.kfl), list tests that are known to fail.

The purpose of this option is to enrich the reporting output so you can monitor the status of certain tests across test runs. If a KFL is specified, the HTML report includes a Known Failure Analysis section. This section provides hypertext links to the tests listed in the KFL. Also, if bug IDs are specified in the KFL the IDs are hypertext linked to a bug tracking system (specified as a URL in File > Preferences > Test Manager > Reporting).

One or more KFLs can be specified as a parameter in the configuration editor. KFLs can also be specified from the command line.

L

Last Test Run View

FilterA [filter](#) that displays the results of those tests and folders included in the last test run either in views of the [test tree](#) or in test reports.

Log LevelA descriptive criteria (Critical, Warning, Monitoring Info, and Debug Info) applied to each message within a log.

M

N

Not RunThe test is not filtered out but the JT harness has not yet run it.

The JT harness displays Not Run icons for tests that have not *yet* been run. Folders containing tests that have not been run are displayed with the Not Run icon only when they do not also contain tests or folders with [Error](#) or [Failed](#) results.

O

P

Parameter FilesLegacy files used to configure how the harness runs legacy test suites on your system. Parameter files use the file name extension `.jtp`.

Although parameter files are deprecated, the harness provides support for those test suites that use parameter files. Current test suites do not use or support the parameter files.

PassTest results determined by the JT harness to meet passing criteria.

The JT harness displays Passed icons for tests that the test suite has determined have passing results and for folders containing only tests with passing results.

Port NumberA number assigned to the JT harness that is used to link specific incoming data to an appropriate service.

Prior StatusA [filter](#) used to restrict the set of tests in a test run based on the last test result information stored in the [test result](#) files (`.jtr`) in the work directory.

Use the configuration editor or command line to enable the Prior Status filter for a test run.

Progress MonitorA dialog box that displays detailed information about the current configuration of a test run. Information displayed in the Progress Monitor is not altered by [view filter](#) settings.

Q

R

Report DirectoryThe directory in which the harness writes test reports.

The location of the report directory is set in the GUI or from the command line by the user when generating test reports.

S

Standard ValuesThe Quick Set mode of the Configuration Editor displays the standard values of a configuration.

T

TabbedA window style in which the JT harness [desktop](#) is a single top-level window that displays all JT windows as tabbed panes.

Test CaseA subsection inside of a test. The terminology for a 'test case' varies among test harnesses, but in this harness, a test is a larger entity than the test case. A test contains zero or more test cases; a test with no test cases is simply a basic test entity in this harness. The 'test' is the primary entity rendered in the main tree display, summaries, etc. 'Test cases' are currently only recognized in limited areas of the harness.

Test DescriptionMachine readable information that describes a test to the JT harness so that it can correctly process and run the related test. The actual form and type of test description depends on the attributes of the test suite. When using the JT harness, the test description is a set of test-suite-specific name-values pairs.

Each test in a [test suite](#) has a corresponding test description that is typically contained in an HTML file.

Test EnvironmentA collection of [configuration values](#) derived from [environment entries](#) in the configuration file that provide information used by test suite specific plugin code about how to execute and run each test on a particular platform.

When a test in a legacy [test suite](#) is run, the harness gives the script a test environment containing environment entries from configuration data collected by the configuration editor. See [configuration](#).

For legacy test suites, the environment entries were read from an environment file. Use of environment files is deprecated, but the harness continues to provide support for test suites that use environment files. See [environment file](#).

Current test suites do not use or support environment files.

Test ManagerThe JT harness window used to configure, run, monitor, and manage tests from its panels, menus, and controls.

The Test Manager window is divided into two panes. It displays the folders and tests of a test suite in the tree pane on the left and provides information about the selected test or folder in the information panes on the right.

A new Test Manager window is used for each test suite that is opened.

Test PathsThe locations of the test folders and tests in the [test tree](#) specified in the Configuration Editor for running tests.

Test paths are used to specify the tests in a specific branch of the test tree or to specify a specific test to run. The harness walks the test tree and runs all specified tests (unless otherwise [filtered out](#)) that it finds.

Use the configuration editor to set the test paths listed in the test run configuration.

Test Result FilesContains all of the information gathered by the JT harness during a test run.

The test result files (.jtr) are stored in a cache in the [work directory](#) associated with the test suite.

You can view the test result files in a web browser configured to use the JT harness ResultBrowser servlet.

Test Run FiltersInclude or exclude tests in a test run. Tests are included or excluded from test runs by the following means:

- [Exclude lists](#)
- [Keywords](#)
- [Prior status](#)

Test run filters are set using the Configuration Editor or the command-line interface.

Test ScriptA script used by the JT harness, responsible for running the tests and returning the status (pass, fail, error) to the harness. The test script must interpret the test description information returned to it by the test finder. The test script is a plug-in provided by the test suite. In the GUI, the Test Manager Properties dialog box lists the plug-ins that are provided by the test suite.

Test SuiteA collection of tests, used in conjunction with the JT harness, to verify compliance of the licensee's implementation of the technology specifications. A test suite must be associated with a [work directory](#) before the harness can run its tests.

Test TreeThe hierarchical representation of the folders and tests in a [test suite](#).

The test tree is displayed in the [Test Manager](#) window and uses colored status icons to indicate the test status of the folders and tests. Use [view filters](#) to specify the folders and tests whose test status are displayed in the test tree.

U

V

View FiltersInclude or exclude the results of tests in views of the [test tree](#).

View filter settings only change the Test Manager display and do not include or exclude tests from a test run. Use the [test run filter](#) settings to include or exclude tests from a test run.

W

Work DirectoryA directory associated with a specific [test suite](#) and used by the JT harness to store files containing information about the test suite and its tests.

Until a test suite is associated with a work directory, the JT harness cannot run tests.

X

Y

Z

Index

Symbols

.jtx files, 99

A

accessing

 UsersGuideonline, 4

add Exclude List files, 122

agent, 12

Agent Monitor tool, 29, 148

All Tests View Filter, 58

appearance preferences

 desktop, 19

Audit Test Results window, 83

auditing test results, 202

B

Bad Checksum panel

 Test Results Auditor window, 86

Bad Result File panel

 Test Results Auditor window, 86

Bad Test Cases panel

 Test Results Auditor window, 87

Bad Test Description panel

 Test Results Auditor window, 87

Bookmarks, 110

browser

 exclude list, 173

 contents, 174

 test details, 174

report, 190

test environment, 171

defined in environment, 173

defined in file, 173

Entry Name, 173

Value, 173

Test Manager Properties, 175

browsing test information, 151

bug prefix URL, 23, 186

button bar (tool bar), 40

C

changing configuration values, 94

changing tests to run, 118

Clear Results

 test tree pop-up menu, 54

configuration

 creating a new, 92

 creating a template, 116

 test manager properties, 177

configuration checklist, 171

Configuration Editor

 Question Mode, 66

 File menu, 67

 Help menu, 69

 index pane, 70

 More Info pane, 71

 question pane, 70

 Recent Configuration, 67, 75

 Search menu, 68

 View menu, 69

 Question Mode view

 Keywords pane, 102

 setting test execution values, 107

Standard Value, 71
Configuration Editor window
 Question Mode
 Bookmarks menu, 67
configuration file
 changing values, 94
 editing values, 95
Configure menu, 36
configuring a test run, 89
Create Report tabbed panes, 32
creating a configuration, 92
creating a template, 116
creating merged reports, 198
creating test reports, 179
Current Configuration view filter, 56
Current Template view filter, 58
Custom view filter, 59
 edit, 60
 specify tests, 61
 use exclude lists, 63
 use keywords, 61
 use prior status, 62
 use test suite filter, 63
 using, 63

D

desktop
 appearance preferences, 19
displaying
 configuration checklist, 171
 online information, 23
 Question Log, 175
 test manager properties, 175
 test tree pop-up menu, 50
displaying reports, 190

E

editing Quick Set values, 95
exclude list
 latest, 101, 123
 other, 101, 124
Exclude List browser, 173
Exclude List contents, 174
Exclude List files, 99
Exclude List test details, 174
execution order, 22

F

File menu, 14
Files tab
 viewing, 163
filters
 view, 55
folder icons, 48
folder information
 Test Manager, 154
folder result status icon, 48
folder run status icon, 48

G

getting started
 GUI, 11
GUI, 11
 tools, 28

Help
 button, 24
 menu, 24
help F1 key, 24
Help menu, 17
HTML Files tab, 184
HTML report options, 183

I

icons
 folder, 48
 result status, 48
 run status, 48
 test, 49
 result status, 50
 run status, 49

information area
 Test Manager, 44

initial files, 96

K

Keywords
 run filter, 102, 125
Keywords pane
 Configuration Editor
 Question Mode view, 102
 Template Editor, 125

KFL, 184, 185, 186
KFL report bug prefix, 23, 186
KFL reports, 186, 187, 188, 189
known failure analysis, 186

L

Last Test Run View Filter, 56
latest exclude list, 101
log viewer, 80

M

markers, 110
menu
 Configure, 36
 desktop
 File, 14
 Help, 17
 Tool, 16
 Windows, 17
 test tree pop-up, 50
 clear previous test results, 54
 execute, 51
 override current configuration, 52
 refresh test suite contents, 52
menus, 14
monitor, progress, 41
monitoring a test run, 143
monitoring output logs, 147
multiple configurations, 113
Multi-Selection Tab, 159

N

number of
 failed tests, 156
 passed tests, 156
 tests filtered out, 156
 tests not run, 156
 tests selected to run, 156
 tests with errors, 156
number of tests
 total, 156

O

online UsersGuide
 accessing', 4
online UsersGuide', 3

options, tool tip, 20
order, 22

P

plug-ins
 test manager properties, 177
Preferences dialog box, 18
progress indicator, 44
 elapsed time, 44
Progress Monitor, 41
 Memory, 43
 Progress area, 42
 Tests in Progress, 43
 Time, 43

Q

Question Log, 175
Question Mode view
 setting
 concurrency, 108
 time factor, 109
Quick Pick test execution
 test tree pop-up menu, 51
Quick Set Mode, 71
Quick Start, 4

R

Refresh Test Suite Contents
 test tree pop-up menu, 52
remote agent, 12
remove Exclude List files, 122
Report Browser, 190
Report Converter Tool, 30
Report Converter Tool window, 30
report directory, 189
report files, 189
reports
 KFL
 New Passed, 187
 test, 178
resolving configuration-template conflicts, 132
Restore Tools State on Start, 21
run filter
 Keywords, 102, 125
run tests

start, 142
running tests
Test Manager window, 139

S

security note, 11
setting
 concurrency, 108, 130
 test execution values, 107, 129
 time factor, 109, 131
setting preferences, 18
shutdown options, 21
site administration, 114, 116
specify tests to run, 96
standard values
 Tests pane, 96
starting a test run, 142
stopping a test run, 148
Summary information, 156
 number of test
 filtered out, 156
 not run, 156
 selected to run, 156
 total, 156
 number of tests
 errors, 156
 failed, 156
 passed, 156
Summary panel
 Test Results Auditor window, 85

T

template
 Tests pane, 118
Template Bookmarks, 134
Template Editor
 editing test execution values, 129
 Keywords pane, 125
 Question Mode, 74
 File menu, 75
 Help menu, 77
 index pane, 78
 More Info pane, 79
 question pane, 78
 Recent Configuration, 67, 75
 Search menu, 76
 View menu, 77

Quick Set Mode, 79
setting
 concurrency, 130
 time factor, 131
Template Editor window
 Question Mode
 Bookmarks menu, 75
templates, 114
templates, editing, 116
templates, loading, 138
Test Description tab, 162
Test Environment browser, 171
 defined in environment, 173
 Defined in file, 173
 Entry Name, 173
 Value, 173
test icons, 49
test information
 Test view, 160
Test Manager
 Configuration tab, 164
 Error test results, 158
 Failed test results, 158
 Filtered Out tests, 159
 folder view, 154
 information area, 44
 Not Run tests, 159
 Passed test results, 158
 Summary information, 156, 157
 number of failed tests, 156
 number of passed tests, 156
 number of tests not run, 156
 number of tests with errors, 156
 subtotal, 156
 test filtered out, 156
 total, 156
Test Run Messages, 166
 message list, 167
 Result message, 168
Test view, 160
test manager
 properties, 175
 configuration, 177
 plug-ins, 177
 test suite, 176
 work directory, 177
Test Manager status line, 64

Test Manager tool, 34
Test Manager window
 browsing test information, 151
 progress indicator, 44
 elapsed time, 44
 progress bar, 44
 running tests, 139
Test Description tab, 162
Test Run Details tab, 165
 property names, 165
 values, 166
test tree, 46
test reports, 178
test result status icon, 50
test results
 auditing, 202
Test Results Auditor window
 Bad Checksum panel, 86
 Bad Result File panel, 86
 Bad Test Cases panel, 87
 Bad Test Description panel, 87
 Summary panel, 85
test run
 monitoring, 143
 start, 142
 stopping, 148
Test Run Messages, 166
 message area, 170
 message list, 167
Output Summary message, 168
Result message, 168
 summary message, 168
 Test Result message, 169
test run status icon, 49
test status
 Error, 158
 Failed, 158
 Filtered Out, 159
 Not Run, 159
 Passed, 158
 Summary information, 157
test suite
 test manager properties, 176
Test Suite Errors
 viewing, 177
test tree, 46
Test view, 160

tests
 running, 139
tool
 Test Manager, 34
tool bar, 40
Tool menu, 16
tool tip options, 20
tool, Agent Monitor, 29, 148
tools
 GUI, 28
troubleshooting, 205
 output overflow
 , 210
reports
 moving, 211
 viewing, 211
 writing, 211
running tests, 207
 tests that fail, 209
 tests with errors, 208
running the harness, 207
viewing test results, 209
troubleshooting a test run, 149

U

User'sGuide
 accessingonline', 4

V

view filter, 55
 All Tests, 58
 Current Configuration, 56
 Current Template, 58
 Custom, 59
 Last Run, 56
viewing source file list, 163
viewing Test Suite Errors, 177

W

window
 Audit Test Results, 83
Windows menu, 17
work directory
 test manager properties, 177
work directory status line, 64

