

# **Retek<sup>®</sup> Integrated Store Operations<sup>™</sup> 11.0**

## **Crystal Reports Installation Guide**



---

**Corporate Headquarters:**

Retek Inc.  
Retek on the Mall  
950 Nicollet Mall  
Minneapolis, MN 55403  
USA  
888.61.RETEK (toll free US)  
Switchboard:  
+1 612 587 5000  
Fax:  
+1 612 587 5100

**European Headquarters:**

Retek  
110 Wigmore Street  
London  
W1U 3RW  
United Kingdom  
Switchboard:  
+44 (0)20 7563 4600  
Sales Enquiries:  
+44 (0)20 7563 46 46  
Fax:  
+44 (0)20 7563 46 10

The software described in this documentation is furnished under a license agreement, is the confidential information of Retek Inc., and may be used only in accordance with the terms of the agreement.

No part of this documentation may be reproduced or transmitted in any form or by any means without the express written permission of Retek Inc., Retek on the Mall, 950 Nicollet Mall, Minneapolis, MN 55403, and the copyright notice may not be removed without the consent of Retek Inc.

Information in this documentation is subject to change without notice.

Retek provides product documentation in a read-only-format to ensure content integrity. Retek Customer Support cannot support documentation that has been changed without Retek authorization.

The functionality described herein applies to this version, as reflected on the title page of this document, and to no other versions of software, including without limitation subsequent releases of the same software component. The functionality described herein will change from time to time with the release of new versions of software and Retek reserves the right to make such modifications at its absolute discretion.

Retek® Integrated Store Operations™ is a trademark of Retek Inc.

Retek and the Retek logo are registered trademarks of Retek Inc.

This unpublished work is protected by confidentiality agreement, and by trade secret, copyright, and other laws. In the event of publication, the following notice shall apply:

©2004 Retek Inc. All rights reserved.

All other product names mentioned are trademarks or registered trademarks of their respective owners and should be treated as such.

Printed in the United States of America.

## Customer Support

### Customer Support hours

Customer Support is available 7x24x365 via email, phone, and Web access.

Depending on the Support option chosen by a particular client (Standard, Plus, or Premium), the times that certain services are delivered may be restricted. Severity 1 (Critical) issues are addressed on a 7x24 basis and receive continuous attention until resolved, for all clients on active maintenance. Retek customers on active maintenance agreements may contact a global Customer Support representative in accordance with contract terms in one of the following ways.

Contact Method	Contact Information
----------------	---------------------

E-mail	support@retex.com
--------	-------------------

Internet (ROCS)	<a href="https://rocs.retek.com">rocs.retek.com</a> Retek's secure client Web site to update and view issues
-----------------	---

Phone	+1 612 587 5800
-------	-----------------

Toll free alternatives are also available in various regions of the world:

Australia	+1 800 555 923 (AU-Telstra) or +1 800 000 562 (AU-Optus)
France	0800 90 91 66
Hong Kong	800 96 4262
Korea	00 308 13 1342
United Kingdom	0800 917 2863
United States	+1 800 61 RETEK or 800 617 3835

Mail	Retek Customer Support Retek on the Mall 950 Nicollet Mall Minneapolis, MN 55403
------	---

### When contacting Customer Support, please provide:

- Product version and program/module name.
- Functional and technical description of the problem (include business impact).
- Detailed step-by-step instructions to recreate.
- Exact error message received.
- Screen shots of each step you take.

# Contents

<b>Windows installation and configuration of Crystal Desktop and Administrative Console Interface .....</b>	<b>1</b>
Prerequisites .....	1
Deploying the Crystal Enterprise Launchpads and Crystal Management Console on Tomcat .....	1
Integrating SIM with Crystal Enterprise 10.....	2
Additional Prerequisites .....	2
Install the SIM Business View in Crystal Enterprise Server.....	2
Install SIM reports with Crystal .....	3



# Windows installation and configuration of Crystal Desktop and Administrative Console Interface

## Prerequisites

- Install JDK 1.4.2\_0X
- Set the JAVA\_HOME environment variable if it is not already there.
- Install Tomcat 4.1.30 (The Tomcat install directory will be referred to as %CATALINA\_HOME% in this document.
- Install Crystal Enterprise 10 and Crystal Reports Client on your computer. These products must be installed as a user with administrative privileges.

## Deploying the Crystal Enterprise Launchpads and Crystal Management Console on Tomcat

- 1 Unzip the reporting.zip file to a staging directory on your machine. This directory will be known as INSTALL\_DIR going forward.
- 2 Shut down Tomcat if it is running. Type %CATALINA\_HOME%\bin\shutdown in the Command Prompt window. If running as a services, shutdown the Tomcat service
- 3 Copy the customized retekCrystal.war file from the INSTALL\_DIR\war folder into the %CATALINA\_HOME%\webapps\ folder Once Tomcat is restarted, the retekCrystal.war file will be expanded into the webapps folder. The parameter and print application is located under the retekCrystal folder. This step creates Crystal user launch pad
- 4 Open the file %CATALINA\_HOME%\conf\server.xml using a text editor such as Notepad.

Add the following line directly above the line <!-- Tomcat Examples Context -->:

```
<Context path="/crystal" docBase="C:\Program Files\Crystal  
Decisions\Enterprise 10\  
java\applications\webcompadapter.war" debug="0" reloadable="false"/>
```



**Note:** If you install Crystal Enterprise in a location other than the default installation directory of C:\ProgramFiles\Crystal Decisions\Enterprise 10, adjust the path descriptions to match your actual install directories.

- 5 Save server.xml after it has been edited.
- 6 Add C:\Program Files\Crystal Decisions\Enterprise 10\win32\_x86\ to the PATH environment variable. (This directory contains Crystal Enterprise DLLs that the WCA uses.)
- 7 Copy the Java archive file cewcanative.jar from C:\Program Files\Crystal Decisions\Enterprise 10\java\applications) to %CATALINA\_HOME%\shared\lib.
- 8 Restart Tomcat by typing %CATALINA\_HOME%\bin\startup at the command prompt.

- 9 Access the Crystal Management Console by loading <http://servername:8080/crystal/enterprise10/adminlaunch> and clicking on Crystal Management Console. For *servername*, substitute the name of the machine where you installed Tomcat. If you chose to use a port number other than the default value, substitute that value for 8080.
- 10 Log on to the Crystal Management Console (CMC) as Administrator. By default, the Administrator account has no password.
- 11 Go to the Crystal Applications area of the CMC, and click Web Desktop.
- 12 On the Properties tab, ensure that the WCA context path is set to /crystal.
- 13 Click Update.
- 14 Restart Tomcat by typing %CATALINA\_HOME%\bin\startup at the command prompt. Restart your server if you are running Tomcat as a NT services.
- 15 To test the Crystal Enterprise User Launchpad, open a web browser and type <http://servername:8080/crystal/enterprise10/desktoplaunch> in its address bar. For *servername*, substitute the name of the machine where you installed Tomcat.
- 16 The Crystal Enterprise User Launchpad should open.
- 17 To log on to the Java version of the Crystal Enterprise web desktop, click the Crystal Enterprise link.
- 18 To test the Crystal Enterprise Admin Launchpad, open a web browser and type <http://servername:8080/crystal/enterprise10/adminlaunch> in its address bar. For *servername*, substitute the name of the machine where you installed Tomcat.

## Integrating SIM with Crystal Enterprise 10

### Additional Prerequisites

Oracle 9.X client must be installed on the desktop

### Install the SIM Business View in Crystal Enterprise Server.

- 1 Click Start/Program/Crystal Enterprise 10/Business View Manager.
- 2 Log on to the Crystal Enterprise server as the Administrator. System is the name of the machine you are using and the default password for Administrator is blank
- 3 On the menu bar, click Tool/Import Business View and select the ISO 104 BusinessView.xml file to import (this is located in INSTALL\_DIR\reports).
- 4 Once the ISO Business View import is complete, expand the SIM folder (under “Repository Explorer”) and open the ISO 10.4 database connection by double clicking on it.
- 5 On the properties browser on the lower left hand side corner, change the Username, Password and Connection to point to your SIM environment and save once the information is entered. If you do not see the Property Browser, check “Object Explorer” under the “View” menu.



## Install SIM reports with Crystal

- 1 Log on to the Crystal Enterpriser as user Admin by accessing the URL <http://servername:8080/crystal/enterprise10/adminlaunch> . Click on “Users” and a new user called SIM . Repeat Step 2 for each of the reports in the INSTALL\_DIR/reports directory
- 2 Open the Crystal Desktop by selecting Start/Program/Crystal Reports 10 Tools/Crystal Reports 10.
- 3 When prompted to login to the Crystal Enterprise, click ‘cancel’(it may prompt for this several times). Ignore any error messages.
- 4 Open the report, select “File” from the menu and click on ‘save as’
- 5 Ignore any error warnings and click the ‘save’ button.
- 6 When the “Save As” screen appears, click the ‘Enterprise’ folder on the left and then it will instruct you to login.
- 7 Log in as Administrator and expand the ‘User Folders’. Select the ‘SIM’ folder and save the report. (the SIM folder was created when the new user was created in Step 1).
- 8 Once the reports have loaded, build the views required by the report by logging in to the ISO database and running each of the sql scripts in INSTALL\_DIR/sql .