



Siebel Sales Handheld Guide

Version 7.8

May 2005

Siebel Systems, Inc., 2207 Bridgepointe Parkway, San Mateo, CA 94404
Copyright © 2005 Siebel Systems, Inc.
All rights reserved.
Printed in the United States of America

No part of this publication may be stored in a retrieval system, transmitted, or reproduced in any way, including but not limited to photocopy, photographic, magnetic, or other record, without the prior agreement and written permission of Siebel Systems, Inc.

Siebel, the Siebel logo, UAN, Universal Application Network, Siebel CRM OnDemand, TrickleSync, Universal Agent, and other Siebel names referenced herein are trademarks of Siebel Systems, Inc., and may be registered in certain jurisdictions.

Other product names, designations, logos, and symbols may be trademarks or registered trademarks of their respective owners.

PRODUCT MODULES AND OPTIONS. This guide contains descriptions of modules that are optional and for which you may not have purchased a license. Siebel's Sample Database also includes data related to these optional modules. As a result, your software implementation may differ from descriptions in this guide. To find out more about the modules your organization has purchased, see your corporate purchasing agent or your Siebel sales representative.

U.S. GOVERNMENT RESTRICTED RIGHTS. Programs, Ancillary Programs and Documentation, delivered subject to the Department of Defense Federal Acquisition Regulation Supplement, are "commercial computer software" as set forth in DFARS 227.7202, Commercial Computer Software and Commercial Computer Software Documentation, and as such, any use, duplication and disclosure of the Programs, Ancillary Programs and Documentation shall be subject to the restrictions contained in the applicable Siebel license agreement. All other use, duplication and disclosure of the Programs, Ancillary Programs and Documentation by the U.S. Government shall be subject to the applicable Siebel license agreement and the restrictions contained in subsection (c) of FAR 52.227-19, Commercial Computer Software - Restricted Rights (June 1987), or FAR 52.227-14, Rights in Data—General, including Alternate III (June 1987), as applicable. Contractor/licensor is Siebel Systems, Inc., 2207 Bridgepointe Parkway, San Mateo, CA 94404.

Proprietary Information

Siebel Systems, Inc. considers information included in this documentation and in Siebel Business Applications Online Help to be Confidential Information. Your access to and use of this Confidential Information are subject to the terms and conditions of: (1) the applicable Siebel Systems software license agreement, which has been executed and with which you agree to comply; and (2) the proprietary and restricted rights notices included in this documentation.

Contents

Chapter 1: What's New in This Release

Chapter 2: Overview of Siebel Sales Handheld

- About Siebel Handheld 13
- Overview of Siebel Handheld Synchronization 14
- Siebel Handheld Synchronization Methods and Architecture 14
 - Handheld Synchronization 14
- Overview of Siebel Handheld Client Application Configuration 15

Chapter 3: Application Development

- Overview of Siebel Handheld Architecture 17
- Unsupported Features for Siebel Handheld 18
- About Defining User Functionality in Siebel Handheld 20
- Configuration Guidelines for Siebel Handheld 20
- About Creating Siebel Handheld Projects 22
- Designing Screens and Views for Siebel Handheld 23
- Configuring User Interface Elements in Siebel Handheld 25
 - Configuring List Applets for the Handheld Client 25
 - Configuring Form Applets for the Handheld Client 26
 - Using Auto Pop-Up Lists in the Handheld Client 27
 - About Home Page Applets in Siebel Handheld 27
 - About Buttons in Handheld 27
 - About the Menu Bar in Handheld 32
 - About Toolbars in Handheld 32
 - About the Status Bar in Handheld 33
 - About Hyperlinks in Handheld 33
- Scripting in the Siebel Handheld Client 34
- Compiling the Siebel Handheld Application 34
- Installing and Setting Up End User Translation Functionality 35
 - Performing Setup for Initial String Translation 35
 - Distributing Translated Strings 36

Configuring Printing from the Siebel Handheld Application	37
Defining Documents for Handheld	37
Designing Print Applets for Handheld	38
Configuring Applets for Printing for the Handheld Application	39
Configuring Print Buttons for the Handheld Application	39
Creating Print Templates for the Handheld Application	40
Configuring Signature Capture Capabilities in Siebel Handheld	40
Enabling Signature Capture	40
Invoking Signature Capture Dialogue Box and Display	41
Signature Capture Dialogue Box and Signature Display	41
Configuring Signature Capture in Activities More Info View in Siebel Handheld	42
Adding a Signature Capture Button in Siebel Tools	43
Signature Capture Applet Control User Properties	44
Testing the Siebel Handheld Application	46
Chapter 4: Application Administration	
Overview of Siebel Handheld Administration Screens	47
Setting Up Users in Siebel Handheld	48
Assigning User Responsibilities to Siebel Handheld Users	49
Creating Siebel Handheld Views	49
Specifying Views for the Handheld Application	50
About Business Component Filters	50
Setting Business Component Filters for Siebel Handheld Users	50
About Business Object Filters	51
Setting Business Object Filters for Siebel Handheld Users	52
About Thread Throttling	53
About Settings in the Handheld Administration Screens	53
Configuring Application Settings for Siebel Handheld	54
Configuring Component Level Settings for Siebel Handheld	59
Administering Barcode Settings for Siebel Handheld	59
Enabling Barcode Scanning in Siebel Handheld	59
Mapping a Button for Socket In-Hand Scan Card	60
Creating New Barcode Definitions for the Handheld Application	60
Enabling Applications Views for Barcode Scanning	64
Example: Process of Creating a New Barcode Definition in the Service Handheld Application	65
About Monitoring Synchronization Sessions for Siebel Handheld	67
Monitoring Synchronization Sessions for Siebel Handheld	68

Obtaining Error Details from Siebel Handheld Synchronization Sessions	68
Obtaining Business Component Information from Siebel Handheld Synchronization Conflicts	69
Obtaining an Audit Trail for Siebel Handheld Synchronization Sessions	69
Acting Upon Synchronization Errors in Siebel Handheld	70

Chapter 5: Data Filtering

Developing Data Filters for Handheld	71
Constructing Business Component and Business Object Filters	72
Business Object Filters	73
Recommendations for Managing Handheld Business Object Filters	73
Companion Sync Deployments	73
Direct Server Sync Deployments	73
Examples of Default Business Object Declarations	74
Designating Visibility	75
Overriding the Popup Visibility	76

Chapter 6: Deployment of Siebel Handheld

Overview of Server Installation in Support of the Siebel Handheld Client	79
Process of Server Installation for Siebel Handheld Direct Server Sync	81
About Siebel Handheld Synchronization Performance and Scalability	84
Providing Synchronization Security with Secure Sockets Layer	85
Process of Installing the Siebel Handheld Application	86
Editing the Handheld Application Installation Configuration File	86
Enabling Handheld User Database Backup	89
Installing Print Templates in the Siebel Handheld Install Directory	91
Setting Up Siebel Handheld Application Installation on a CompactFlash Card	91
Changing the SyncURL on Siebel Handheld Devices	92
Installing the Siebel Handheld Application from External Media	92
Distributing Siebel Handheld Application Patches	93
Deploying Patches to the Handheld Application with Direct Server Sync	93
Deploying Handheld Application Patches with Companion Sync	94
Creating Handheld Application Upgrade Kits for Companion Sync PDA	95
Downloading Patches to the Handheld Device	96

Chapter 7: Synchronization Conflict Handling and Recovery with Handheld

Preventing Synchronization Transaction Conflicts with Siebel Handheld	97
Extended Pick Processing in Siebel Handheld	97
Enabling Extended Pick Processing in Siebel Handheld	98
Insert Failure Processing in Siebel Handheld	100
Recovering Error Data in Siebel Handheld	102

Chapter 8: Installing the Handheld Application

Preparing to Upgrade from a Previous Siebel Handheld Release	103
Installing the Siebel Handheld Application	103
Installing Handheld for Companion Sync Users	103
Installing Handheld for Direct Server Sync Users	105
Reinstalling the Siebel Handheld Application	106
Uninstalling the Siebel Handheld Application	106

Chapter 9: Working with Siebel Handheld Applications

Components of the Siebel Handheld Interface	107
Navigating the Siebel Handheld Interface	110
Navigating a List of Records in the Siebel Handheld Application	111
Entering Data with the Siebel Handheld Application	112
Working with Columns in the Handheld Client	112
Finding and Querying Data in the Siebel Handheld Application	112
About Find in Handheld	113
About Queries in Handheld	113
Printing with the Siebel Handheld Application	114
Exporting Data with the Siebel Handheld Application	114
Setting User Preferences in the Siebel Handheld Application	115
Backing Up and Restoring Data with the Siebel Handheld Client	115
Synchronizing Data on the Siebel Handheld Device	117
Using Siebel Handheld Synchronization with the Handheld Client	117
Using Companion Synchronization with the Handheld Client	118
Using Direct Server Synchronization with the Handheld Client	119
Synchronization Troubleshooting with the Siebel Handheld Client	120
Improving Siebel Handheld Application Performance	121

Chapter 10: Using Siebel Sales Handheld

About Using Siebel Sales Handheld	123
About Managing Contacts in Siebel Sales Handheld	123
Scenario for Managing Contacts in Sales Handheld	124
Adding Contacts in Sales Handheld	124
Associating Contacts with Opportunities in Sales Handheld	125
Managing Accounts in Siebel Sales Handheld	125
Scenario for Managing Accounts in Sales Handheld	126
Creating Accounts in Sales Handheld	126
Associating Activities with Accounts in Sales Handheld	127
Associating Opportunities with Accounts in Sales Handheld	128
Developing Opportunities in Siebel Sales Handheld	128
Scenario for Developing Opportunities in Sales Handheld	129
About Creating Opportunities in Sales Handheld	129
About Sales Methods in Sales Handheld	130
Associating a Contact with an Opportunity in Sales Handheld	131
Associating a Product with an Opportunity in Sales Handheld	131
About Opportunity Quotes in Sales Handheld	132
Managing Customer Relationships in Siebel Sales Handheld	132
About Activities in Sales Handheld	133
Scenario for Managing Activities in Sales Handheld	133
Creating Activities in Sales Handheld	133
Delegating Activities in Sales Handheld	133
Associating Contacts with Activities in Sales Handheld	134
Adding General Activities Using the Calendar in Sales Handheld	134
Developing Quotes in Siebel Sales Handheld	136
Scenario for Developing Quotes in Sales Handheld	136
Creating Quotes in Sales Handheld	136
Using Auto Quote in Sales Handheld	137
Adding Quote Items in Sales Handheld	138
Printing Quotes in Sales Handheld	140
Managing Orders in Siebel Sales Handheld	140
Creating Orders in Sales Handheld	140
Adding Order Line Items in Sales Handheld	141
Entering Terms and Totals in Sales Handheld	142
Tracking Expenses in Sales Handheld	142
Creating an Expense Report in Sales Handheld	142
Submitting an Expense Report in Sales Handheld	143

Appendix A: Troubleshooting

- Installation 145
- Synchronization 146
 - Companion Sync Checklist 146
 - Direct Server Sync Checklist 147
 - Re-synchronizing Problems 148
- Log Files 148
 - Direct Server Sync Log and Output Files 148
 - Companion Sync Log and Output Files 149
 - Handheld Device Log 149
- SQLTrace 151
- End User Error Messages 151
- Web Server Timeout Errors 151
- Handheld Device Timeout Errors 152
- Performance 152

Appendix B: Screens and Views

- Screens and Views 155

Appendix C: Business Components and Classes

- Supported Business Components for Siebel Handheld 159
- Business Component Classes 160
- Applet Classes 161

Appendix D: User Properties and Methods

- User Properties 163
- Methods 163
 - AutoQuote 163
 - AutoOrder 165

Appendix E: Print Tagging Language

- Overview of Siebel Handheld Print Tagging Language 169
 - Applet 170
 - Cell 171
 - Comment 173
 - Divider 173

EndOfLine	174
Footer	175
Format	176
GetCount	177
GetDate	177
GetField	178
GetRegistry	179
GetTime	180
GetTotal	180
Header	181
Page Break	182
Picture	182
SetVariable	184
Static Text	184
Title	184

Using Variables in Print Templates	185
------------------------------------	-----

Appendix F: Print Configuration Settings

Overview of Siebel Handheld Print Configuration Settings	187
MarginBottom	187
MarginLeft	188
MarginRight	188
MarginTop	188
PaperHeight	188
PaperSize	188
PaperWidth	189
PrinterBaudrate	189
PrinterCompressed	190
PrinterDensity	190
PrinterDither	190
PrinterDraftMode	190
PrinterFormFeed	191
PrinterHandshake	191
PrinterOrientation	192
PrinterPort	192
PrinterType	193
Default Printing Settings	194

Index

1

What's New in This Release

What's New in Siebel Sales Handheld

Table 1 lists descriptions of the changes made to this version of the documentation to support Release 7.8 of the software.

Table 1. What's New in Siebel Sales Handheld, Version 7.8

Topic	Description
"Configuration Guidelines for Siebel Handheld" on page 20	Revised and expanded the general guidelines, including screen and view design, for configuring Siebel Handheld applications.
"Performing Setup for Initial String Translation" on page 35	Revised setup procedure for allowing translation capability in Siebel Handheld applications.
"Configuring Signature Capture Capabilities in Siebel Handheld" on page 40	Revised and expanded this topic with information on enabling signature capture, signature display, and the Signature Capture applet control user properties.
"Creating Siebel Handheld Views" on page 49	Revised procedures for creating new views in the Siebel Handheld applications and adding those views to a user's responsibilities.
"About Thread Throttling" on page 53	Added new topic describing the method for allowing the maximum number of concurrent synchronizations.
"Configuring Application Settings for Siebel Handheld" on page 54	Added new topic describing parameter settings in the Administration - Mobile screen.
"Administering Barcode Settings for Siebel Handheld" on page 59	Revised and expanded this topic with information on enabling barcode scanning, mapping a button for the Socket In-Hand Scan Card, and creating barcode definitions.
"Acting Upon Synchronization Errors in Siebel Handheld" on page 70	Added descriptions of user options after encountering synchronization errors.
Data Filtering "Constructing Business Component and Business Object Filters" on page 72 "Examples of Default Business Object Declarations" on page 74	Revised and expanded Data Filtering chapter with examples of business component filter syntax, business object filter syntax, and default business object declarations.

Table 1. What's New in Siebel Sales Handheld, Version 7.8

Topic	Description
Logging Levels "Configuring Direct Server Sync Logging Levels" on page 82 "Configuring Companion Sync Logging Levels" on page 83	Added information on Logging Level parameters and how to configure them.
"Providing Synchronization Security with Secure Sockets Layer" on page 85	Added information on securing the synchronization data stream by using Secure Sockets Layer (SSL).
"Editing the Handheld Application Installation Configuration File" on page 86	Revised and expanded this table of setup.ini parameters and their descriptions.
"Changing the SyncURL on Siebel Handheld Devices" on page 92	Updated information on using SyncURL to allow communication between the handheld synchronization client and the handheld synchronization server.
"Preventing Synchronization Transaction Conflicts with Siebel Handheld" on page 97	Revised the information on Extended Pick processing and handling Insert Failure processing.
"Using Companion Synchronization with the Handheld Client" on page 118	Revised information on performing Companion Sync, including Integrated Sync.
"Adding Quote Items in Sales Handheld" on page 138 "Adding Order Line Items in Sales Handheld" on page 141	Revised information on pricing functionality when adding line items to quotes and orders.
"Companion Sync Checklist" on page 146 "Direct Server Sync Checklist" on page 147	Revised troubleshooting information to help users determine why or when a synchronization has failed.
"Log Files" on page 148	Revised this section on logs and output files to include information on logging Siebel Handheld synchronization errors.
"SQLTrace" on page 151	Added information on enabling and using SQL tracing.
"PrinterType" on page 193	Revised the list of supported printers for Siebel Handheld.

2

Overview of Siebel Sales Handheld

This chapter includes the following topics:

- [“About Siebel Handheld” on page 13](#)
- [“Overview of Siebel Handheld Synchronization” on page 14](#)
- [“Siebel Handheld Synchronization Methods and Architecture” on page 14](#)
- [“Overview of Siebel Handheld Client Application Configuration” on page 15](#)

About Siebel Handheld

Siebel Handheld provides a focused subset of functionality to that of the Siebel Web Client. The Siebel Handheld Client differs from the Siebel Web Client and the Siebel Mobile Web Client in that it uses a selected subset of views, accommodates smaller screen sizes, and has a reduced memory capacity. For a list of functional differences, see [Chapter 3, “Application Development.”](#)

Some features that are available on the Siebel Mobile Web Client are not available on the Siebel Handheld. Scripting and Siebel engines (for example, Pricing and Reporting) are not supported on the handheld. For a list of features that are not supported, see [“Unsupported Features for Siebel Handheld” on page 18.](#)

Some supported features of the Siebel Handheld client are as follows:

- **Application Development with Siebel Tools.** Siebel Handheld applications can be configured in Siebel Tools using the Web Applet Designer. You can take your existing Siebel application and use this as the basis for the Siebel Handheld application, or you can create a new application by using the Siebel Tools application shipped on the Siebel Handheld application DVD. See [Chapter 3, “Application Development,”](#) for more information.
- **Data filtering.** Filtering allows you to specify a subset of data to be used on the handheld device. Filtering is an important feature of a Siebel Handheld deployment because of the relatively large size of the average enterprise database in comparison to the relatively limited memory capabilities of handheld devices. It is important that you allocate sufficient time in the project plan to create and test the handheld filters. See [“Application Development” on page 17](#) for more information.
- **Installation options.** The Siebel Handheld application can be installed on Windows-powered devices in one of two ways. The first is to create a partnership between a desktop or laptop PC and the handheld device using Microsoft ActiveSync. The second is to install the Siebel Handheld application from external media, for example, a Cabinet (CAB) file. Handheld patches can be remotely deployed using PatchAgent. For more information, see [Chapter 8, “Installing the Handheld Application.”](#)

- **Patch Updates.** Siebel Handheld automatically applies the latest software patches to the handheld device when needed. Companion Sync allows users to Synchronize the Handheld Database to the local database on Companion PC and invokes Siebel Remote to synchronize the local database with the server database.

PatchAgent automates the deployment of patches to handheld devices as part of the synchronization process. For more information on PatchAgent, see ["Installing the Siebel Handheld Application from External Media" on page 92.](#)

- **Backing Up and Restoring Data.** The Siebel Handheld application provides database backup functionality. A database restore utility is also included with the application. See ["Enabling Handheld User Database Backup" on page 89](#) for details.

Overview of Siebel Handheld Synchronization

The Siebel Handheld Synchronization (Sync) client synchronizes data between the Siebel Handheld database and the Mobile Web Client database or server database. The synchronization process does the following:

- Updates the Siebel server database with changes made to the Siebel Handheld database
- Updates the database on the handheld device with changes made to the Siebel server database
- Downloads metadata changes, such as object definitions for new or modified screens or views
- Allows users to select filters to limit the amount of data that is downloaded
- Automatically applies the latest software patches to the handheld device when needed

Siebel Handheld Synchronization Methods and Architecture

The following methods can be used to synchronize data on the handheld device with data in the Siebel server database: Companion Sync (CS), Direct Server Sync (DSS) and Direct Server Sync via Proxy (DSSvP). The architecture of these methods is discussed in the following sections.

Handheld Synchronization

A Handheld synchronization server component run on the Siebel application server can accept concurrent synchronization requests from multiple synchronization clients. When connecting directly to a server, the Siebel Handheld Sync client synchronizes its data directly to a server database. Companion Sync allows users to synchronize the Handheld Database to the local database on a companion PC device and invokes Siebel Remote to synchronize a local database with the server database.

In Direct Server Sync mode, the Siebel Handheld Synchronization client uses the HTTP(S) protocol over a network connection to communicate with the handheld synchronization server. Users should configure their handheld devices for communication over the desired network.

A companion synchronization server runs on a companion personal computer with a Mobile Web Client installation and supports synchronization with a data source specified in a client configuration; the database resides on the companion PC.

Companion Sync

Companion Sync allows users to synchronize the Siebel Handheld application and database with a Siebel Remote database on a Mobile Web Client.

Microsoft ActiveSync is used to connect the handheld device and the companion PC through a serial or USB connection. The user launches Siebel Handheld Sync from companion PC or the device. The user can change the default filters using Siebel Handheld Sync.

Direct Server Sync

Direct Server Sync allows users to synchronize their Siebel Handheld application and database directly with the Siebel server. The user connects the handheld device to the Siebel application server through a network connection that uses the HTTP protocol. The connection runs through a IIS Web server to the application server, where the Sync server components are installed and running.

Direct Server Sync via Proxy

Direct Server Sync via Proxy (DSSvP) allows users to synchronize their Siebel Handheld application and database directly with the Siebel server. The user connects the handheld device to the Siebel application server through ActiveSync and the network connection established by the companion PC. The connection runs through a IIS Web server to the application server, where the Sync server components are installed.

Overview of Siebel Handheld Client Application Configuration

The following provides an overview of the configuration process of the Handheld client. Complete the following steps to configure your handheld client application.

To configure the Siebel Handheld client

- 1** Define the user functionality.

Determine which user interface elements (such as screens, views, toolbars, applets, find, and help) will be necessary for your Siebel Handheld Client end users. For more information, see ["About Defining User Functionality in Siebel Handheld" on page 20](#).

2 Configure the Siebel Handheld Client user interface.

The process for configuring user interface elements in the Siebel Handheld Client is the same as that for other Siebel clients. For more information, see ["Configuring User Interface Elements in Siebel Handheld" on page 25](#) and *Configuring Siebel Business Applications*.

3 Identify all eScript or VB script.

Siebel Handheld applications do not currently support scripting, including eScript or VB script. Scripting used in your Siebel application may conflict with your Siebel Handheld application configuration.

4 Compile the new configuration.

For more information, see ["Compiling the Siebel Handheld Application" on page 34](#).

5 Test the new configuration.

Test the configuration, repeating the previous steps, to address any configuration errors.

After completing the Siebel Handheld Client configuration, you are ready to install it on the handheld devices. To install the Siebel Handheld configuration on a handheld device, see the instructions in ["Installing the Siebel Handheld Application" on page 103](#).

3

Application Development

This chapter includes the following topics:

- “Overview of Siebel Handheld Architecture” on page 17
- “Unsupported Features for Siebel Handheld” on page 18
- “About Defining User Functionality in Siebel Handheld” on page 20
- “Configuration Guidelines for Siebel Handheld” on page 20
- “About Creating Siebel Handheld Projects” on page 22
- “Designing Screens and Views for Siebel Handheld” on page 23
- “Configuring User Interface Elements in Siebel Handheld” on page 25
- “Scripting in the Siebel Handheld Client” on page 34
- “Compiling the Siebel Handheld Application” on page 34
- “Configuring Printing from the Siebel Handheld Application” on page 37
- “Configuring Signature Capture Capabilities in Siebel Handheld” on page 40
- “Testing the Siebel Handheld Application” on page 46

Overview of Siebel Handheld Architecture

The process for configuring a Siebel Handheld Client has a few differences, described in this chapter, from the process for configuring other types of Siebel clients.

NOTE: Readers should familiarize themselves with the Siebel client configuration process described in *Configuring Siebel Business Applications* before attempting to configure the Siebel Handheld Client.

The five layers in the Siebel Handheld architecture are comparable to those used on the Siebel Web Client:

Application layer. The application layer starts and closes the application.

User Interface layer. The user interface layer renders the display and interacts with actions of the user.

Object Manager layer. The object manager layer provides a consistent object behavior and interaction between all business objects within the application.

Data Manager layer. The data manager layer maintains an object-oriented abstraction of the native data stored in the data repositories for the benefit of the object manager.

Database layer. The database layer includes the data that Siebel Handheld users access.

Your Administrator configures an application on the Siebel client using Siebel Tools and compiles the Siebel repository (.srf) file. During the synchronization process, information specific to the Siebel Handheld Client is extracted from the Siebel repository file. This information is used to create a repository metalanguage (.rml) file, which is downloaded to the handheld device.

The repository metalanguage file contains the layout information for the handheld device but not the database layer. The database layer is generated in the transport file called dbfile.txt, which is downloaded and imported to the handheld database (siebelDB.sdf).

For more information on Siebel Tools, see *Using Siebel Tools*.

Unsupported Features for Siebel Handheld

The differences between configuring user interface elements for the Siebel Web Client and the Siebel Handheld Client are shown in [Table 2](#).

Table 2. Configuring Siebel Client User Interface Elements

Client	Siebel Tools	SWT Template Files	Specialized Algorithms
Siebel Web Client	Yes	Yes	No
Siebel Handheld Client	Yes	No	Yes

The following are not supported in Siebel Handheld applications:

- The following applet types are not supported:
 - Chart
 - Explorer
- Group boxes are not supported. See [“Group Boxes” on page 26](#) for more information.
- Alarm Manager is not supported. Therefore, if an alarm check box is added to an applet and the check box is selected, no alarm sounds.
- The base time zone is determined by the system settings on the server and cannot be changed on the handheld device.
- Alphabet tabs are not supported.
- Scripting is not supported. However, any scripts on the business components will be executed during synchronization.
- Siebel Workflow is not supported.

See the following topics which outline, more specifically, other unsupported features.

Multi-Value Groups (MVG)

The Multi-Value Group applet is not supported on the Siebel Handheld Client; however, the Multi-Value Group relationship is supported. The Multi-Value Group (MVG) control button does not appear on fields in Siebel Handheld Client applications. Instead, MVGs can be implemented as parent-child views. As a result, MVG fields are not editable within the parent record. In the Siebel Web Client, addresses of accounts are added, deleted, or edited through the Business Address MVG applet. However, in the Siebel Sales Handheld Client, these functions must be done through a Business Address child applet with an Account applet as its parent.

On the handheld device, all MVG fields are displayed as read-only, with the primary record visible. The first record will be displayed if the primary record is not specified. If you have an application or business requirement that requires the user to view or update all the records in the MVG, you must configure a separate view for that MVG. For example, the Address field in the Accounts or My Accounts view is an MVG. In the Siebel Handheld Client that field is read-only and displays the primary record. In order for the handheld user to see and update the addresses, the new Address view is configured in Siebel Tools. This new Address view is visible in the Show drop-down list.

Functions

Siebel Handheld applications support most of the calculated fields and operations used in the Siebel Web applications with a few exceptions. See [Table 3](#) for a list of the unsupported functions.

Table 3. Unsupported Functions

Function Name
BCHasRows
DockingNodeId
DockingNodeName
DockingNodeRoutId
EAILookupExternal
EAILookupSiebel
EXISTS
GetHQInstanceId
GetHQInstanceName
GetNumBCRows
GetProfileAttr
GetXAval
IsDocked
LanguageName
LocaleName

Table 3. Unsupported Functions

Function Name
LookupMessage
LookupTranslation
NOT
RepositoryId
RepositoryName
RowIdToRowNum
ToolsLanguage

The NOT key word is not supported on Booleans. Use the != operator instead. For example, "Active" != "Y".

The RowIdToRowNum function is supported differently in the handheld applications than in the Web applications. In Web applications, RowIdToRowNum converts a row Id to a numeric value. In the handheld applications, the row ID itself is returned.

About Defining User Functionality in Siebel Handheld

The first step in configuring a Siebel Handheld Client is to determine which user interface elements are necessary. Siebel Handheld Client users have different requirements from Siebel Web Client users. Keep in mind the differences in display size, memory capacity, and input methods between handheld devices and larger computers, such as desktop computers.

The goal is to create applications that are easy for your end users to use and which take advantage of the strengths of the handheld device platform. Because of processing speed, memory limitations, and form factor differences, you should only include those user interface elements that are necessary for users to complete their job responsibilities.

Configuration Guidelines for Siebel Handheld

There are a few general guidelines you should bear in mind when configuring for the Siebel Handheld application. Use these guidelines when you design any new objects for the Siebel Handheld Client. This approach facilitates a logical separation of the Siebel Handheld Client user interface elements from the Siebel Web Client user interface elements.

- Identify User Activities
 - To conserve memory (and thereby improve performance) and ease navigation, identify business processes that are required by end users and develop applications that support these processes.

- If more than one type of user needs a Siebel Handheld Client application, it is preferable to divide the application into multiple responsibilities rather than give all possible users access to all available screens and views. Responsibilities are fully configurable by the application developer.
- Do not include additional functionality that is not required to reside on the device.
- Limit the number of screens and views
 - Keep the number of views in your application to 30 or fewer. Determine critical business processes that the handheld will support and only pick the views that are necessary and are compliant with your business requirements.
 - Limit the number of views within a screen to 12 or fewer to keep the View drop-down list concise.
 - Limit the number of screens to 6 or fewer to keep the Screen drop-down list concise.
 - Keep screen names to about 15 characters or fewer, so that they fit in the Screen drop-down list. The number of characters is a general guide because characters vary in width.
 - Keep view names to about 30 characters or fewer so that they fit in the View drop-down list. The number of characters is a general guide because characters vary in width.

- Limit the number of applets for each view

Design each view so that it has one or, at most, two applets. Limiting the number of applets enhances performance, and enriches the user experience.

NOTE: Some views contain three applets. Use the toggle button to navigate between the two child applets.

- Limit the number of columns and fields for each applet to minimize scrolling

Consider the following when designing your applets:

- Design applications that contain as few screen and view hierarchy levels as possible. In a Web-based application, you may have views with many applets, and the user toggles between the applets. However, for handheld applications, create more views with fewer applets to allow users to quickly find information with a minimal amount of toggling.
- Include the most important fields and columns that a user needs to see at a glance before scrolling. For example, if you have a form applet that is a parent, include only needed fields to avoid scrolling.
- If you are using a list applet, determine how wide it needs to be.
- Design each applet so that it only contains columns and fields that are required for end-user tasks.
- Consider moving required and editable fields into visible area of the applet where users can enter data and would not have to scroll. Because there is less screen space on a handheld device than on a laptop or desktop, the most important data should be immediately visible.
- The Date Column can be formatted to show only the date instead of Date and Time where Time is not relevant. This saves the user from having to scroll.
- To minimize horizontal scrolling, limit the number of columns displayed in a list applet to no more than ten.

- There is no limit on the number of fields in form applets of single-applet views. However, to minimize scrolling, keep the number of fields to 20 or fewer.
- Use a form applet for the parent for each parent-child view.
- In a multi-applet view, limit the number of fields in form applets to five or fewer. Add additional fields only if the field width is short. For example a check box field.
- Reduce the number of fields if the fields are multi-line, for example, a Comments box that contains three lines of text.
- Do not include read-only check boxes in form applets. It is very difficult for users to discern that the check box is not editable.
- Do not add pick applets or set the Runtime property to true for Read-Only fields that have a picklist value associated to them. This will improve overall extraction time, synchronization time and dbfile.txt file size since the process will not be forced to extract all the picklist values for these fields.
- Keep query names to about 15 characters or fewer, so that they fit in the Queries drop-down list. For example, North American Organization is too long for a query name, so you should change it to a shorter name, such as N. American Org. The number of characters is a general guide because characters vary in width (for example, W is wider than i).
- For each screen, create a single-applet More Info view. Create this applet as a form applet. For example, for the Contacts screen, create a More Info view that has the Contacts form applet only.
- For each screen, create a view called My * or All * as a single list applet view. For example, for the Activities screen, create a My Contacts view that has the Contacts list applet only.
- Design Data Filters
 - Limit the size of the dbfile.txt file to less than three megabytes (MB). The RDBMS on the handheld device is approximately three times the size of dbfile.txt. If the data files are so large that they cannot be imported into the database with the available memory, users cannot successfully synchronize their data. See [Chapter 5, "Data Filtering"](#) for information on how to design data filters to limit the amount of data that is synchronized to the handheld.
 - When working with assessment creation functionality, you need to name your templates in such a way that they will filter only the needed templates that will be downloaded to the device. Without properly setting up filters, all templates will be downloaded to the device.

About Creating Siebel Handheld Projects

The Siebel Handheld projects appear in the list of projects in Siebel Tools; when Project is selected in the Object Explorer, the list of projects is displayed in the Object List Editor.

Use a naming convention that allows you to easily identify applications, screens, views, and applets belonging to a particular Siebel Handheld application. This allows you to locate all the object definitions in a Siebel Handheld application by querying on the name in the Object List Editor. For example, all of the Siebel Handheld Client screens, views, applets, toolbars, and menus use either an SHCE prefix (for example, SHCE Sales Account List view) or a CE suffix. Use the Object List Editor to query for views that contain the prefix SHCE or the suffix CE; doing so displays all of the Siebel Handheld Client views.

If you create a new Siebel Handheld application, create a new suffix or prefix to identify the name of the application and each screen, view, and applet name. For example, you could use PPC_SHCE for an application.

Designing Screens and Views for Siebel Handheld

Each view in a Siebel Handheld application can display a maximum of two applets at a time, regardless of the number of applets in the view. If there are more than two applets in a view, the user can navigate to additional applets by toggling.

Screen Allocation

The amount of screen space available for applets is determined by the type of applets in the view. Two applets are stacked above one another. A parent form applet in a two-applet view displays multiple fields on a screen. Users use the scroll bar to navigate. The form applet dynamically resizes if there are fewer than five fields and, therefore, does not waste screen display space with empty lines. The maximum number of fields that are displayed at one time is configurable by setting the Max Parent Applet Size preference in the User Preferences dialog. See ["Setting User Preferences in the Siebel Handheld Application" on page 115](#) for more information on this user preference.

Toggling Between Multiple-Applet Views

The Siebel Handheld Client application displays up to two applets at one time. If the view has only one applet, the applet takes up the entire display area. For views with two or more applets, the first two applets in the view are displayed, and the user toggles to see the other applets. The first applet is always displayed and the second applet changes as you toggle.

By default, the user toggles by choosing the View > Toggle menu item. In addition, it is recommended that you provide a toggle button as a visual cue to the end user that there are additional applets. Add a toggle button to each applet except the first applet. Identify the button with a Toggle caption and set `methodInvoked` to `ToggleApplet`.

Drill-Down Only Views

Some views may be drill-down only views—that is, they can only be accessed by navigating from another view. These views should not be accessible through the Show drop-down list. However, when the end user navigates to the view, the view title appears in the Show drop-down list. To configure a drill-down only view, set the view title as you would for any other view and set the `ScreenMenu` property to `FALSE`. See *Configuring Siebel Business Applications* for more information.

Applet Focus Behavior

When navigating between views, there may be instances when you need to override the default behavior for giving focus to an applet

The GotoView method is used to navigate from one view to another. A button control is added to the applet in the view you want to navigate from, the button's methodInvoked property is set to GotoView and the button's View property is set to the view that is to be created. When the GotoView method is executed, it builds the specified view. If the view includes a parent and child applet, GotoView gives focus to the child applet. This is the desired behavior in most instances when you are simply navigating from one view to another.

If the desired behavior is to navigate to a new view and, additionally, to create a new record, then you must use the GotoViewNewRecord method. This method calls two methods; first it calls GotoView, and then it calls NewRecord, which creates a new record in the new view.

In some instances the default behavior of these methods does not produce the intended behavior. For example, in the Orders view of the Service Requests screen, when you tap the Create New Order button, it takes you to the Order Details view, which contains a parent form applet (Service Request Order) and a child list applet (Service Order Entry Line Item). In this instance, when the Create New Order button's GotoViewNewRecord method is executed, you want a new order to be created. However, the default behavior is to give focus to the child applet rather than creating a new record in the parent applet. Therefore, you need to override the default behavior of GotoView with the control user property OverrideDefaultApplet, and set the value to the applet that you want to give focus. The valid values are 0 (parent) and 1 (child). For example, if you create a button labeled "Create Service Request Order," you would define user properties shown in [Table 4](#):

Table 4. User Properties

Name	Value
View	SHCE Service Order Line Items View
OverrideDefaultApplet	0

Views with Associated Print Templates or Reports

Print templates are text files that you design and create for printing. After creating a print template, you associate it with an applet. When an end user chooses to print from a view, the print template that is associated with the applet is automatically selected and used for printing. Follow these guidelines when creating print templates:

- Only one print template can be associated with an applet.
- The print template name for a particular display applet is registered in the Mail Template property in the Applet object associated with the applet.
- The template must be placed in the Templates directory.
- The template name that goes into the Mail Template property should not include a path name or extension. For example, if the full path of the template is \Program Files\Siebel Handheld\Templates\InvoiceTemplate.txt, you would enter only the root name InvoiceTemplate in the property field.

- The template file itself must have a .txt extension on the device.

For more information, see [Appendix F, "Print Configuration Settings."](#)

Configuring User Interface Elements in Siebel Handheld

When configuring user interface elements on the Siebel Handheld Client, also consider the processing speed and memory constraints of handheld devices. The constraint on processing speed affects the performance of a handheld device. The performance of a handheld device is also related to the number of screens and views downloaded to the handheld device. Because handheld devices are not meant to provide the same functionality as larger devices, such as laptops, the number of screens and views must be kept to a minimum on the handheld device.

Due to size constraints on handheld devices, the Siebel Handheld Client displays user interface elements differently from the Siebel Web Client. Consider these differences when configuring the Siebel Handheld Client application. For example, Siebel Handheld Client does not support an alphabetical index.

Configuring List Applets for the Handheld Client

You configure list applets and list columns for Siebel Handheld applications the same way you configure them for other Siebel applications.

Recommended Strategy for Configuring List Applets

The recommended strategy when configuring the Siebel Handheld Client is to use the list applets for record navigation and to rely on form applets to provide the record details.

The following are additional guidelines to follow when designing list applets:

- Configure specific list applets for your Siebel Handheld application, rather than reusing Siebel Web Client list applets.
- Remove all but the essential list columns. Because there is limited screen area to display list columns, omit all unnecessary columns to minimize horizontal scrolling.

You may either remove the columns from the application or set the Show in List property on the column to FALSE. These two methods are different in the following ways. If the columns are removed from the application, these data won't be downloaded to the handheld device, which keeps the handheld data and a minimum and, in turn, optimizes synchronization performance. If the Show in List property on the column is set to FALSE, the data is still downloaded to the device but is not shown by default. This second approach, though without the synchronization optimization benefit, does allow convenience for the user who wants to customize visible columns. You should take these concerns into account when setting up users.

- Reorder the remaining list columns so that the most frequently used columns are furthest to the left.

- Reduce the default width of the list columns so that more columns can be viewed at one time.
- Use hyperlinks to ease navigation by enabling users to drill into a form applet.

These changes can minimize the amount of horizontal scrolling and column reordering that users must do. Limiting the number of list columns to those that are essential minimizes the amount of data downloaded to the device, resulting in faster synchronization times and more economical use of device memory.

NOTE: All required fields on form and list applets appear with an asterisk (*). If an administrator specifies that a field is required, the field appears with an asterisk in the user interface.

Use Siebel Tools to modify, or rearrange List Columns. For more information on the List Column options, see *Configuring Siebel Business Applications*.

Configuring Form Applets for the Handheld Client

The handheld uses a specialized algorithm to format and display form applets. Due to the display limitations on the device, only one pair of label and field controls are displayed on each row of the form, regardless of the layout shown within Siebel Tools.

Layout Sequence

When configuring for the handheld device, the Applet Web Template Items in the Applet Web Template determine the controls that appear on a form applet. The layout of form applets on the handheld device is determined by the HTML Sequence field set on control objects.

The HTML Sequence field determines the screen layout of a handheld device. Controls are ordered from top-to-bottom based on their HTML Sequence property values. Label and control pairs that do not fit on the same line as other label and control pairs wrap to the next line.

Labels

Keep field labels in applications short (approximately 12 characters or fewer, depending on the character width). Use abbreviations where possible. Labels that are too long are truncated.

Group Boxes

Group boxes are not supported and are not displayed in form applets, even if they are added in the Web Applet Designer. Therefore, reword the field labels to include group box information if necessary. For example, you may have two group boxes on the form, one labeled Ship To and another labeled Bill To. Each group box includes a field named Address. Because group boxes are not supported, the Ship To and Bill To labels are lost, and two fields with the identical Address label remain. Therefore, you must rename the Address labels "Ship To Addr" and "Bill To Addr" or some other label that distinguishes them.

Using Auto Pop-Up Lists in the Handheld Client

Sometimes when a user encounters a new view, he or she must perform an action, such as filling in a required field by selecting a value from a pop-up list. Rather than requiring the end user to tap the control to open the pop-up list, you can configure the view so that the pop-up list automatically opens when the end user gets to that view. To configure a pop-up list to open automatically, add the user property on the applet with Name set to AutoPopupField. Depending on the type of applet, this property is set differently:

- For list applets, set the AutoPopupField property to the Business Component field name.
- For form applets, set the AutoPopupField property to the name of the control.

About Home Page Applets in Siebel Handheld

To configure a Home Page applet, create an applet that has controls of HTML Type Button only. Use the following guidelines in creating your Home Page applets:

- Set the MethodInvocation property of these controls to GotoView. Then add a user property for the control, and set the Name parameter to "View" and set the Value parameter to the view name.
- Set the Caption field.
- Set the HTML Sequence field according to the order in which the buttons are laid out on the device. The buttons appear on the Home Page applet of the handheld device, laid out in rows of three buttons.
- Set the class property of the Applet to CSSFrameCEHome.

About Buttons in Handheld

Set the HTML Type field on buttons to Button, MiniButton, PushButton, or MiniButtonEditNew. All of these HTML Types map to the same button control on the handheld device.

Buttons with text labels on them are sized to the minimum width required to fit the text on the buttons.

NOTE: You cannot use scripting to augment the button functionality in handheld applications.

You may add buttons as long as the method invoked is supported by the class or superclass of the frame or business component. You may also remove buttons from an applet. Be careful when removing buttons because you may alter the behavior of your application in unintended ways. [Table 5](#) describes the behavior of buttons on the different screens. Use this table to guide your decisions about removing buttons from your handheld applications.

For more information of button functionality, see [Appendix D, "User Properties and Methods."](#)

Table 5. Button Functionality

Screen	View	Button	Button Functionality
Accounts	Views	Measurements	Goes to the Asset Measurements view.
Accounts	Views	Warranties	Goes to the Asset Warranties view.
Accounts	Views	Components	Goes to the Asset Sub-Components view.
Browser	Views	Check Substitute	Checks for substitute parts for the current part. Navigates to the Part Browser Substitutes view.
Billings	Invoice Line Items	Cancel	<p>Only applies to Invoices in which Type = Receivable.</p> <ul style="list-style-type: none"> ■ Changes the invoice status to Cancelled. ■ Changes the Order status to Open. ■ Opens the Order Line Items view. <p>If the order cannot be found, displays a warning message.</p>
Billings	Invoice Line Items	Pay	Opens the Invoice Payments view.
Billings	Invoice Line Items	Print	Prints an invoice.
Billings	Invoice Line Items	Visit Home	Opens the Outlet Visits view, Activities screen. The focus is on the visit in progress for the account on the invoice.
Billings	Invoice Payments	Print	Prints a payment receipt.
Billings	Invoice Payments	Visit Home	Opens the Outlet Visits view, Activities screen. The focus is on the visit in progress for the account on the invoice.

Table 5. Button Functionality

Screen	View	Button	Button Functionality
Billings	Invoice Line Items	Deliver	<p>If Type = Receivable:</p> <ul style="list-style-type: none"> ■ Checks the inventory to see if there is sufficient stock to fill the order. If the requested quantity exceeds the on-hand stock, a message is displayed informing the user that there is insufficient inventory. ■ Compares the order total against the account's available credit. If the order exceeds the available credit, a warning message is displayed. ■ Changes the invoice status. ■ Decrements inventory. ■ Decrements available credit. <p>If Type = Payable:</p> <ul style="list-style-type: none"> ■ Creates a credit memo. ■ Increments inventory by the total quantity shipped. ■ Changes the invoice status to Credited.

Table 5. Button Functionality

Screen	View	Button	Button Functionality
Orders	Order Line Items	Invoice	<ul style="list-style-type: none"> ■ Checks the inventory to see if there is sufficient stock to fill the order. If the requested quantity exceeds the on-hand stock, a message is displayed informing the user that there is insufficient inventory. <p>The user is asked if he or she wants to update the order based on the available quantity. If the user chooses to continue, the system adjusts the Qty and Bonus Qty fields so that the totals do not exceed the available stock.</p> <p>Otherwise, the user is returned to the Order Line Items view where he or she can edit the quantities.</p> <ul style="list-style-type: none"> ■ Compares the order total against the account's available credit. If the order exceeds the available credit, a warning message is displayed. ■ Changes the order status to Billed. ■ Generates an invoice for the order. ■ Cleans the order of all zero-quantity items. ■ Opens the Billings screen, Invoice Line Items view.
Orders	Order Line Items	List Products	Lists all products in the account's Product Distribution list that are flagged as orderable (Retail Order flag).
Order	Order Line Items	Print	Prints the order.
Outlet Visits	My Outlet Visits	End Visit	<ul style="list-style-type: none"> ■ Records the current timestamp in the Actual End field. ■ Changes the status. ■ Makes the record read only. ■ Calculates the actual duration of the visit.

Table 5. Button Functionality

Screen	View	Button	Button Functionality
Outlet Visits	My Outlet Visits	Prepare Visit	<ul style="list-style-type: none"> ■ Verifies that a retail order activity is assigned to a selected visit. ■ If a retail order activity exists, an order header is created for the account and products that are flagged as orderable for the account are listed as line items in the order. ■ If a retail order product does not exist for the selected visit, an order header is created for the account.
Outlet Visits	My Outlet Visits	Start Visit	<ul style="list-style-type: none"> ■ Records the current timestamp in the Actual Start field. ■ Changes the status. ■ Opens the Visit Activities view.
Outlet Visits	Visit Activities	End Activity	<ul style="list-style-type: none"> ■ Records the timestamp in the Actual End field. ■ Changes the status. ■ Makes the record read only.
Outlet Visits	Visit Activities	End Visit	<ul style="list-style-type: none"> ■ Records the current timestamp in the Actual End field. ■ Changes the status. ■ Makes the record read only. ■ Calculates the actual duration of the visit.

Table 5. Button Functionality

Screen	View	Button	Button Functionality
Outlet Visits	Visit Activities	Start Activity	<ul style="list-style-type: none"> ■ Records the current timestamp in the Actual Start field. ■ Changes the status. <p>Opens one of the following views:</p> <ul style="list-style-type: none"> ■ If Type = Retail Assessment, opens the Accounts screen, Assessments view. ■ If Type = Retail Audit, opens the Retail Audit view. ■ If Type = Retail Order, opens the Orders screen, Order Line Items view. ■ If Type = Stock Transfer, opens the Activities screen, Product Movement view. ■ If Type = Review Billings, opens the Accounts screen, Invoices view. ■ If Type = Return Order, opens the Accounts screen, RMAs view.
Outlet Visits	Visit Activities	Start Visit	<ul style="list-style-type: none"> ■ Records the current timestamp in the Actual Start field. ■ Changes the status.
RMAs	RMA Line Items	Credit	<ul style="list-style-type: none"> ■ Changes RMA status to Billed. ■ Generates a credit note. ■ Opens the Billings screen, Invoice Line Items view.

About the Menu Bar in Handheld

The menu object definition in the Siebel repository that is implemented in handheld applications is named SHCE Generic. The default menu bar configuration for the Siebel Handheld Client includes the following menus: File, Edit, View, and Help. You may remove or rename menus on the menu bar, but you cannot add new menus. You may reorder the menu items by changing the Position property for the menu items. Generally, use the default menu bar configuration for all of your Siebel Handheld Client applications.

About Toolbars in Handheld

This section describes how to configure the toolbar for your application.

Table 6 shows the supported toolbar functions.

Table 6. Supported Toolbar Functions

Toolbar Functions
Back, Forward
New Record
New Query, Execute Query
Next Record, Previous Record, First Record, Last Record
Minimize/Maximize
Delete Record

The default toolbar can be configured in Siebel Tools by configuring the SHCE Main toolbar object. SHCE Main is the main toolbar that is downloaded to the handheld device. If a toolbar named SHCE Main does not exist in your repository, a default toolbar, *Main*, is downloaded instead.

The SHCE Main toolbar contains the default buttons for the device: Back, Forward, New Record, New Query, and Execute Query. Change the order of the buttons on the display by modifying the Position property of the toolbar items. Remove a toolbar button by deleting it or making it inactive.

You can add additional default buttons to the toolbar by creating toolbar items whose Command property matches the name of an active bitmap in the SHCE Command Icons bitmap category. Do not add bitmaps to the SHCE Command Icons bitmap category because only those commands, which are already provided, are supported on the device. No additional commands are supported. You can remove a bitmap or make a bitmap inactive if you do not want it to appear in the Customize Toolbar dialog box.

You can change the bitmap for a toolbar by reimporting the bitmap from the SHCE Command Icons bitmap category.

An end user can personalize the toolbar by selecting View > Toolbar.

For more information on toolbars, refer to *Configuring Siebel Business Applications*.

About the Status Bar in Handheld

The status bar is located above the toolbar. The status bar displays the status of an applet with focus, including the applet title and record item count (for example, Contacts: 1 of 13).

About Hyperlinks in Handheld

Configuring a drilldown, or clicking a hyperlink or dynamic hyperlink in the Siebel Handheld Client, is performed the same way as with other Siebel clients. For more information on configuring drilldowns, see *Configuring Siebel Business Applications*.

Scripting in the Siebel Handheld Client

The Siebel Handheld Client does not execute Siebel Visual Basic (VB) or Siebel eScript scripting.

The Siebel Handheld Client application runs Siebel VB or Siebel eScript scripts and specialized business component logic at synchronization time, rather than in real time on the handheld device. This has significant consequences in applets and controls, because scripts attached to applets and controls are ignored.

CAUTION: Be aware of the following additional issues with respect to scripts and validation:

- **Deactivating scripts.** Do not deactivate existing scripts in Siebel Tools to make the handheld device or the synchronization process accept data it is excluding. Errors may occur within the Siebel Web Client or elsewhere where these scripts are run.
- **Calls to user interface methods.** When a business component script makes a call to a user interface method (such as MsgBox), the script cannot be executed, and the record update, deletion, or addition is rejected during synchronization. Strictly speaking, a script attached to a business component should not interact with the user interface.

Any Siebel Visual Basic code should be restricted to the business component level. Applet-level Siebel Visual Basic will not execute and, therefore, should not be written for the Siebel Handheld Client application. As a substitute to using Siebel Visual Basic on the Siebel Handheld Client application, for real-time execution, use the following business component user properties:

- BC/Field Read Only Field...for making fields or business components read-only dynamically.
- Pickmap for fields on the picklist.

Do not use message boxes or prompts in the Siebel Visual Basic code used in conjunction with the Siebel Handheld Client application business components. If the business component is shared between the Siebel Handheld Client application and a laptop, use the following construct to determine if the code is being executed in real time on the laptop or during synchronization:

```
'ActiveViewName is only available when the script is called real time on the laptop
If (TheApplication.ActiveViewName<>"") then
MsgBox"....."
End If
```

- Business component level scripting will be executed during synchronization. Error handling may need to be enhanced if the business component is shared between the handheld application and the laptop.

Compiling the Siebel Handheld Application

Compiling the repository for the Siebel Handheld Client is identical to compiling on the Siebel Web Client. For more information, see *Using Siebel Tools*. For deployment to production, always perform a full compilation. This assumes that you have organized all of your handheld object definitions in one project or a limited set of projects.

When you compile your application, a Siebel repository file (.srf) is created and put in the destination directory you specified during the compile procedure. Make this .srf file the source of repository information for the Siebel Handheld test client machine, defining all Siebel applications for that client, when you move it to your local \Siebel\objects directory.

It is strongly recommended that you make a backup of the existing .srf file in your local \Siebel\objects directory before overwriting it with the new one. That way, if you make an error or you want to revert to the original application, you have a backup that you can easily restore. Versioning for the repository is tracked, and if the .cfg, schema, or repository files have changed, the sync process will automatically rebuild the .rml and schema. For more information, see *Using Siebel Tools*.

Installing and Setting Up End User Translation Functionality

End User Translation functionality provides you with the ability to translate the text strings within the Siebel Handheld application. The translation process should be undertaken during the development cycle and once completed your development team can then package the translated strings for distribution.

The translation process requires the generation of a file of strings from the handheld binaries which are then translated and distributed to the user base. This file, userstr.txt, containing the translated strings is then used to override the strings within the existing handheld binaries. Therefore, you will be required to build a copy of userstr.txt into the installation media for your handheld application.

The translation string file is version specific so you must repeat this process every time you upgrade your Siebel Handheld application.

Performing Setup for Initial String Translation

In order to perform the initial string translation you must perform the following steps prior to installation:

To setup Siebel Handheld application for initial string translation

- 1 In the Handheld installation directory, add the following two lines to the setup.ini file

```
[EndUserLocalization]
```

```
UserDefinedLang=Y
```

- 2 Install the Siebel Handheld application.

During application initialization and the subsequent startup, the file 'userstr.tmp' is generated within the ApplicationDataDirectory (by default this is \Program Files\Siebel Handheld). This file is generated upon startup whenever the UserDefinedFlag is set to Y within the handheld registry and an existing userstr.txt cannot be found.

- 3 Copy the generated file over to the computer where you will be performing the string translation.

- 4 Translate the strings as required and remove any untranslated strings from the file.

For example, given the following section of exported strings:

```
33872|HTML\  
33873|Tab delimited text file\  
33874|Export\  
33875|Format:\  
33876|Only Active applet\  
33877|All applets in view\  
33878|Output file name\  
33879|Browse...\  
33880|And paste output to clipboard\  
33881|And open file\
```

Translate the required strings and remove any untranslated strings as follows:

```
33873|Archivo delimitado por tabulaciones\  
33874|Exportar\  
33875|Formato:\  
33876|Sólo el applet activo\  
33877|Todos los applets de la vista\  
33878|Nombre del &archivo de salida:\  
33880|Y pegar salida en el &portapapeles\  
33881|Y &abrir el archive
```

NOTE: Strings 33872 and 33879 were removed from the userstr.txt as they were not required to be translated.

- 5 Save the file as userstr.txt in a UNICODE file format and then copy back into the ApplicationDataDirectory on the handheld device.
- 6 After restarting the Siebel Handheld application, the translated strings are read from userstr.txt in place of the strings included in the handheld binaries.

Distributing Translated Strings

Once you have generated and tested the userstr.txt file of translated strings, you should include this file in the installation media for the Siebel Handheld application.

To distribute translated strings

Create a new language sub-directory named `UserDefinedLanguage` within the Siebel Handheld installation directory from which end user devices are installed and which contains the `setup.exe`.

This directory with the name `UserDefinedLanguage` will exist alongside the language sub-directories shipped with the application. The new `userstr.txt` file should be placed in this subdirectory.

Upon installation of the Siebel Handheld application, the custom file will be placed in the `ApplicationDataDirectory` of the destination device along with the usual handheld files.

Configuring Printing from the Siebel Handheld Application

Users may print from any view in the application. However, they are not necessarily printing what they see on their screen. They may print a portion of the data they view or data that is not viewable at the time.

A print template defines the document that is to be printed. After the template has been defined, it must be associated with an applet in a view.

This section provides information on the following topics:

- Defining documents
- Designing print applets
- Configuring applets for printing
- Creating print buttons
- Creating print templates

Defining Documents for Handheld

Defining documents for printing includes several steps:

- Determine the documents your users need to print.
- Determine the views from which they are most likely to print the documents.
- Lay out the document for printing.

Determining which documents users will need and the views from which they are most likely to print requires that you have a good understanding of the users' day-to-day work.

Whether the existing applets in a view include most of the required data or only a small portion is a secondary consideration. It is not likely that a printout of the existing applets, which are formatted for an electronic PDA interface, will provide an acceptable or usable printed document. In most instances, you need to create additional applets that are specifically used for printing data.

The printed document will be composed of several applets which are added to the view. The applets pull the data from the underlying business components. These applets, in turn, direct the data to the print templates discussed in [Appendix E, "Print Tagging Language."](#)

Designing Print Applets for Handheld

The print template references applets associated with the view and is how you specify what data appears in the printed document. For information on print templates, see [“Creating Print Templates for the Handheld Application” on page 40](#). As you design your applets, you should be aware of the print specifications of the printers used in the field. Portable printers typically print on two-inch or four-inch wide paper. You need to design your applets so that the data fits within the limits of the paper width. Keep your documents simple so that they work with different sizes of paper. The following are some guidelines to use when designing your applets to accommodate the smaller paper sizes.

Form Applets

Data from only one business component can be displayed on each line in your document. When you design your form applets, keep in mind that you can display a maximum of two columns of data in form applets. You can specify that each column of data is preceded by an optional caption column. This means you can have up to four columns displayed in your document—two data columns and two caption columns. Alternatively, you may have no captions, and simply display one or two columns of data.

The ratio between caption and data columns is, respectively, 35 percent and 65 percent. This is a fixed relationship that cannot be customized in the template.

Limitations on multiple columns in printed output are largely hardware dependent. In printing 7 fields on a 40 column printer, physical limitations allow only 4-5 characters per field $(40 - (7-1))/7 = 4.85$. To print more than 4 columns, an 80 column printer is recommended. Generally, the capabilities of impact printers are lower than those of Thermal printers.

List Applets

When specifying the width of a column, you can either specify it with a unit of measurement or as a percentage of the total page width. For example, you can specify that the first column is 20 mm, and the second column is 40 mm. If the width of the paper you print to is narrower than 60 mm, the column widths automatically adjust to fit the printable width as a proportion of the specified width. Therefore, the first column will always be 33 percent, and the second column will be 67 percent of the paper width. The minimum width for a column is 8 mm, which includes a 3 mm gutter margin between columns.

You can specify any number of columns in your list applet. However, if the width of the column is less than 8 mm, the application ignores the column and does not print it.

On narrow paper widths, data from a field may not all fit on one line. Data that does not fit can be specified, in the Applet tag, to wrap to the next line and keep wrapping until the data in that field is completely displayed. The printable width of the page is equal to the paper width minus the left and right margins ($\text{PaperWidth} - [\text{LeftMargin} + \text{RightMargin}]$). These parameters are set in the setup.ini file. For more information on setting these parameters, see [Appendix F, “Print Configuration Settings.”](#)

Configuring Applets for Printing for the Handheld Application

Configure print applets as you would any other applet using Siebel Tools. In addition, set the following properties for each applet in the view.

- Set the HTML Popup Dimension value to 0x0.

The 0x0 setting hides the applet from the end user who should not see the applet that is used to generate the document. Exposing these applets would complicate a product that is tightly configured for an effective and efficient workflow on a small mobile device.

NOTE: For compatibility with previous versions, Siebel Systems continues to support the name, *Popup Dimension*, for this property. However, it is recommended that you use *HTML Popup Dimension*.

- Set the name of the Mail Template to be the name of the print template file. For more information on the print template file, see ["Creating Print Templates for the Handheld Application" on page 40](#). For more information on the Mail Template property, see ["Views with Associated Print Templates or Reports" on page 24](#).

Configuring Print Buttons for the Handheld Application

While users can use the File > Print menu option to print a document, it is helpful to include a Print button on the applet to give users a visual reminder that it is possible to print from a particular view.

When you design your applets, keep the following in mind when deciding where to place the print button:

- Add the print button to the applet that is visible to the user. Do not add the print button to the print applet, which the user never sees.
- Consider what the desired behavior is when determining the placement of a print button.

For example, in a parent-child view, you may want to add the print button to the parent applet to ensure that the print button is always enabled. This is not necessarily true if the print button is placed on the child list applet. If there are no items in the list applet, the print button is disabled, and the end user cannot print from that view. If you only want the end user to print when there are list items, then placing the button on the child list applet is appropriate.

To configure a print button

- 1 From Siebel Tools, add a control to the print applet and specify HTML Type = Button.
- 2 Set Method Invoked = Print.
- 3 Set the Display Name property of the button. Generally, this is set to Print.

Creating Print Templates for the Handheld Application

Once you have identified and created the necessary views, you are ready to create print templates. A print template is a text file that includes instructions for printing a document. It specifies the data to be printed, document layout options, and text formatting. These instructions are specified using a print tagging language that is described in [Appendix E, "Print Tagging Language."](#)

Configuring Signature Capture Capabilities in Siebel Handheld

You can configure the Siebel Handheld Application to capture, view, and print signatures. The following sections provide details on configuring signature capture:

- ["Enabling Signature Capture" on page 40](#)
- ["Invoking Signature Capture Dialogue Box and Display" on page 41](#)
- ["Signature Capture Dialogue Box and Signature Display" on page 41](#)
- ["Configuring Signature Capture in Activities More Info View in Siebel Handheld" on page 42](#)
- ["Adding a Signature Capture Button in Siebel Tools" on page 43](#)
- ["Signature Capture Applet Control User Properties" on page 44](#)

Enabling Signature Capture

Enabling signature capture requires implementing the required supporting field and column definitions, adding a signature control to the applet and, if required, configuring an applet button through which the signature capture dialogue box can be invoked. A field can be configured as a signature control in any list or form applet. Multiple signature controls can be added to a single applet. Once captured, signatures are converted to an ASCII encoding data and stored with the Siebel database as ASCII text.

When enabling Signature Capture, the following basic configuration is required:

- The Business Component field mapped to the signature control should be of Type DTYPE_NOTE
- The underlying Table Column on which the Business Component field is based on Physical Type LONG
- The Applet Control should have a Control User Property called "Signature" with a value "Y". The Control's HTML Type property should be set to "Field"

NOTE: The Applet Control by default does not redisplay the signature data if there is data in the underlying business component field. In this case, you will see the field as read only and will not be able to see the signature that was captured. To redisplay signatures, add another Control User Property called "Show Data" with a value "Y". With this additional configuration, the control is still read-only, but you will be able to see the signature that was captured. For a full list of User Properties available for configuring signature capture, see ["Signature Capture Applet Control User Properties" on page 44.](#)

Invoking Signature Capture Dialogue Box and Display

There are two ways to invoke the Signature Capture dialogue box or Signature Display. By default, the basic configuration specified in the Enabling Signature Capture section allows you to invoke the signature capture dialogue box or display a signature using the (...) ellipses button.

You may also use the following basic configuration to invoke the Signature Capture dialogue box or display with the Applet Signature button.

- Create a new Control with properties HTML Type = MiniButton, Method Invoked = StartSignature
- Add a Control User Property to the MiniButton control to indicate the signature field in the business component (for example, the field that is being used to store signature in the business component on which the applet is based).

For examples, see ["Configuring Signature Capture in Activities More Info View in Siebel Handheld"](#) on page 42 and ["Adding a Signature Capture Button in Siebel Tools"](#) on page 43.

Signature Capture Dialogue Box and Signature Display

The Signature Capture dialogue or display box consists of three controls in the client area: header, signature, and footer. A toolbar displays various buttons depending on the existence of signature data.

Initially, when signature data does not exist or has not yet been captured, the user sees a single line of text within the field control that reads Not Signed. Once the signature capture dialogue box or signature display is invoked, this message appears at the bottom of the screen. The Clear and Cancel buttons are also enabled, while the Accept button is disabled. Once the Signature area within the dialogue box is populated, the Accept button is automatically enabled. [Table 7](#) describes the functionality around these three buttons.

Table 7. Signature Capture Dialogue Box Buttons

Button	Description
Accept	Tap this button to commit the signature to the database.
Clear	Tap this button to reset and clear the signature field.
Cancel	Tap this button to discard the signature and close the display.

Once the signature is committed (for example, signature captured and accepted in the database), the user sees a single line of text "x Signed x" within the applet field control.

The Header and Footer is a line or unlimited number of lines of text in one or more paragraphs. The specific Header or Footer values that appear as well as how they appear in the dialogue box is controlled by a set of user properties. See ["Signature Capture Applet Control User Properties"](#) on page 44.

Configuring Signature Capture in Activities More Info View in Siebel Handheld

The following example provides detailed steps to configure signature capture in Activities More Info View in SIA Sales Handheld. The Activities More Info View has one applet 'SIS HH Activity Entry Applet - CE', which is based on the Action Business Component, which in turn is based on S_EVT_ACT Table. The following example shows how to configure a field within the Action Business Component called Signature, which is based on a new column created from S_EVT_ACT_X Table. To enable basic signature capture (for example, no header or footer), follow these steps:

- 1 In Siebel Tools, add an extension column to the table S_EVT_ACT_X.

For this Field	Add This Value
Name	SIGNATURE
User Name	Signature
Type	Extension
Nullable	TRUE
Physical Type	Long
Length	0
Cascade Clear	Ignore
Transaction Log Code	TRUE
Status	Active
Sequence	999
Comments	Extension Column for Activity Signature Capture

- 2 Add a field to Action business component with the following values:

For this Field	Add This Value
Name	Signature
Join	X_EVT_ACT_X
Column	SIGNATURE
Text Length	16,383
Type	DTYPE_NOTE
Use Default Sensitivity	TRUE
Comments	Custom Field added for Signature Capture

- 3 Add control to applet. For this example, you will add the control to the 'SIS HH Activity Entry Applet - CE'.

For this Field	Add This Value
Name	Signature
Caption	Signature
Caption String Reference	SBL_SIGNATURE-1005113048-35Y
Field	Signature
HTML Display Mode	EncodeData
HTML Row Sensitivity	TRUE
HTML Type	Field
Runtime	TRUE
Text Alignment	Left
Visible	TRUE
Comments	Custom control added to display and invoke Signature Capture.

- 4 Add two Control User Properties to the new 'Signature' control with the following values:

User Property Name	Value
Signature	Y
Show Data	Y

- 5 Add the new control to the Edit Web Template for 'SIS HH Activity Entry Applet - CE'.

You can now invoke the signature capture dialogue box by tapping on the ellipsis (...) on the signature field on the applet.

Adding a Signature Capture Button in Siebel Tools

Optionally, you can also configure the signature capture dialogue box by placing a button on the applet. The following configuration steps provide details on doing this.

To create a new minibutton control

1 Create a new MiniButton control against the 'SIS HH Activity Entry Applet - CE'.

For this Field	Add This Value
Name	SignatureCapture
Caption	Sign
Caption String Reference	SBL_SIGN-1005113047-35W
HTML Type	MiniButton
MethodInvoked	StartSignature
Comments	Custom MiniButton to Invoke Signature Capture.

2 Add a Control User Property to the MiniButton control to indicate the Signature field in the business component:

- Name = SignatureField
- Value = Signature

Signature Capture Applet Control User Properties

The user properties, shown in [Table 8](#), are optional and provide you with the ability to modify the style and layout of the Signature Capture applet.

Table 8. Style and Layout Modification Properties

User Property	Description	Sample Value
Signature	If Y the field becomes a signature field	Y
ShowData	If Y, the signature data can be redisplayed. Setting this User Property to 'N' disables the ellipses in the signature applet control, when there is signature data already existing	Y or N
EncryptKey	Encrypt key string. If this is not specified, an internal mechanism is used to generate the encryption key.	1 and 99999999
WritingGuide	Defines appearance of writing guide in signature control.	Y or N
BorderStyle	Defined the border style of the signature control.	Double
InkColor	Defines the ink color. Uses a Hex format (OxBBGGRR) of blue, green, red.	OxFF0000 (Blue)
InkWidth	Defines ink width	2 (Pen width)

The user properties shown in [Table 9](#) are added to support header and footer display and the save function.

Table 9. Header and Footer Display Properties

User Property	Description	Sample Value
SignatureDataField	This property is used to specify a destination field for the captured signature in scenarios where it differs from the current UI field. When specified, it specifies the name of the business component field that the signature data is fetched from and saved to.	SigDataField
SignatureHeaderField	Specifies the name of the BC field from which the header value is fetched.	SigHeader
SignatureFooterField	Specifies the name of the BC field from which the footer value is fetched.	SigFooter
SignatureHeaderSaveField	Specifies the name of the BC field to which the header value is saved.	SigHeaderSave
SignatureFooterSaveField	Specifies the name of the BC field to which the footer value is saved.	SigFooterSave
MaximumHeaderLines	Specifies the maximum height of the header display control in number of text lines. If the header text exceeds this number, the user needs to scroll down the control to view the rest of the header text. (Default = 4).	4
MaximumFooterLines	Specifies the maximum height of the footer display control in number of text lines. If the header text exceeds this number, the user needs to scroll down the control to view the rest of the header text. (Default = 4).	4
SignatureHeight	Specifies the height of the signature capture control by pixels (default = 80, max = 200).	Integer between 1 and 200.
SignatureDate	If set to Y, the current date is appended below the last line of the footer. The date string is saved to footer save field.	Y
SignatureTime	If set to Y, the current time is appended below the last line of the footer to the right of date if date is specified. The time string is saved to footer save field.	Y
ConfirmAccept	If set to Y, a confirmation message is displayed after accept button is pressed. Otherwise, no confirmation message is displayed.	Y

NOTE: If the content of the Header or Footer exceeds the MaximumHeaderLines or MaximumFooterLines, respectively, then the content can be scrolled vertically using the pen. No scrollbar will be generated.

Testing the Siebel Handheld Application

Before deploying your application to your end users, be sure to thoroughly test the application by synchronizing to a handheld device. The handheld configuration is downloaded to the device where you can test the functionality and verify that you have the desired behavior. Another equally important aspect of handheld testing is to check to see how much data is downloaded to the device. If too many records are downloaded, this increases the length of time it takes to synchronize the handheld device and slows down the application performance. Check the server log file to see how many records are downloaded for each business component. You must turn on logging to capture this information in the log file.

For more information on enabling logging for Direct Server Sync, see ["Configuring Direct Server Sync Logging Levels"](#) on page 82.

For more information on enabling logging for Companion Sync, see ["Configuring Companion Sync Logging Levels"](#) on page 83.

4

Application Administration

This chapter includes the following topics:

- "Overview of Siebel Handheld Administration Screens" on page 47
- "Setting Up Users in Siebel Handheld" on page 48
- "Assigning User Responsibilities to Siebel Handheld Users" on page 49
- "Creating Siebel Handheld Views" on page 49
- "Setting Business Component Filters for Siebel Handheld Users" on page 50
- "Setting Business Object Filters for Siebel Handheld Users" on page 52
- "Configuring Application Settings for Siebel Handheld" on page 54
- "Configuring Component Level Settings for Siebel Handheld" on page 59
- "Administering Barcode Settings for Siebel Handheld" on page 59
- "About Monitoring Synchronization Sessions for Siebel Handheld" on page 67
- "Monitoring Synchronization Sessions for Siebel Handheld" on page 68
- "Obtaining Error Details from Siebel Handheld Synchronization Sessions" on page 68
- "Obtaining Business Component Information from Siebel Handheld Synchronization Conflicts" on page 69
- "Obtaining an Audit Trail for Siebel Handheld Synchronization Sessions" on page 69
- "Acting Upon Synchronization Errors in Siebel Handheld" on page 70

Overview of Siebel Handheld Administration Screens

This chapter is designed to show you how to administer Siebel Handheld. Key tasks are outlined that you can perform using the Administration - Mobile screen. Your organization may follow a different task sequence according to its business requirements.

Following are the views used for administering Siebel Handheld applications. You can access the Administration - Mobile screen through either the Siebel Web Client or Siebel Mobile Web Client.

- **Session Administration:** This view contains a detailed information about user synchronization sessions. Use this view to monitor and investigate handheld user synchronization activities.
- **Server Component Administration:** This view allows you to manage server-level settings for synchronization components. These settings are used by the synchronization engine to extract application definition and user data. These settings will override the application-level settings.

- **Application Administration:** This view lists all the handheld applications available within your enterprise. From this view you can create new application settings and administer settings that have already been created. The contents of the following views are used by the synchronization engine to extract application definition and user data.
 - **Business Component Filters:** Use this view tab to change synchronization filter settings for business components. If you wish to restrict the contents of selected business components to reduce the data set otherwise visible to your users, you can change filter settings in this view.
 - **Business Object Filters:** Use this view tab to define business object level filters, which restrict data that is downloaded to the handheld client upon synchronization.
 - **Settings:** Use this view tab to define parameter settings for your application.
- **Conflict Administration:** This view allows you access selected transaction errors.
 - **Audit Trail:** Use this view tab to obtain information about action taken on a particular data conflict. Audit Trail must first be enabled for the conflict data. The business components are Handheld Transaction Error and Handheld Txn Error Message.
 - **Business Components:** Use this view tab to see business component information associated with a particular data conflict.
 - **Error Details:** Use this view tab to get detailed information about specific data conflicts. You are also able to take particular action on any given conflict.
- **Barcode Administration:** This view allows you to create new barcode definitions for your handheld applications.
- **User Administration:** This view allows you to manage user-specific settings, such as business object and business components filters, that filter the data that display to the user. The data sets contained in these user views are used by the synchronization engine to extract application definitions and user data. The Siebel Handheld application is populated by these data when the user performs synchronization. These settings override the server component-level and application-level settings.
 - **User Business Components:** Under this view tab, you can set user-specific sync filter directives for business components. These settings override application-level settings.
 - **User Business Objects:** Under this view tab, you can set user-specific filters for business objects. In this setting, you limit the data set that is downloaded, at the time of sync, to the Handheld client. These settings override application-level settings.
 - **User Settings:** Under this view tab, you can control user-specific settings which override server component-level and application-level settings.
- **Barcode Enabling:** In this view you can enable barcode scanning for chosen views in the Siebel Handheld application.

Setting Up Users in Siebel Handheld

To set up users on a Siebel Handheld application, perform the following tasks:

- [“Assigning User Responsibilities to Siebel Handheld Users” on page 49](#)

- [“Creating Siebel Handheld Views” on page 49](#)
- [“Setting Business Component Filters for Siebel Handheld Users” on page 50](#)
- [“Setting Business Object Filters for Siebel Handheld Users” on page 52](#)

Assigning User Responsibilities to Siebel Handheld Users

You must create user accounts and assign responsibilities and passwords for each handheld user. The steps are the same as those for creating user accounts, assigning responsibilities and passwords for the Siebel Web Client. See *Applications Administration Guide* for more information on this topic.

Creating Siebel Handheld Views

The handheld synchronization engine extracts views based on configuration (SRF) and the responsibility set up in the Application Administration view.

To configure a new view in your handheld application, follow the list below. Knowledge of Siebel Tools is required to perform these tasks.

- 1 Create the new view in Siebel Tools. For information on creating views, see *Configuring Siebel Business Applications*.
- 2 Add that view to the handheld screen. For more information on adding views to screens, see *Configuring Siebel Business Applications*.
- 3 Add the screen to the handheld application if required. For more information on adding screens to applications, see *Configuring Siebel Business Applications*.
- 4 Compile the project. For information on compiling projects, see *Using Siebel Tools*.
- 5 Add the new view to the Siebel Handheld user’s responsibility. See [“To add a handheld view to a user’s responsibility” on page 49](#).

To add a handheld view to a user’s responsibility

- 1 Launch the Web Client application that uses the same database that the Siebel Handheld application synchronizes with.
- 2 Choose Navigate > Site Map > Administration-Application > Views.
- 3 Add the new views.
- 4 In the Responsibilities view, associate each view with the appropriate handheld responsibility.
- 5 Add appropriate users to the responsibility.

NOTE: For more detailed instructions on adding views and associating views with responsibilities, see *Applications Administration Guide*.

Specifying Views for the Handheld Application

The Siebel Handheld application uses a small subset of views used in the Siebel enterprise application. Because there are memory resource constraints on handheld devices, it is recommended that you compile an SRF to extract only those views that are used on the device.

The combination of the SRF and the user's responsibility determines which views are extracted. The handheld device only extracts views whose parent screen is included in the handheld application and are part of the user's responsibility.

About Business Component Filters

Business component filters are used in some cases to restrict the size of extractions that otherwise might be excessive. They suppress the extraction of business component records. Business component filters should be employed with discretion because excessive filtering can cause server data integrity problems.

Business component filters can be specified at either the Application level or the User level, but not at the Component level. They should not be specified at the user level outside of your test environment, and once tested should be migrated to the Application level.

If you are configuring for handheld synchronization, a suggested practice, is to start with no business component filters at all. Attempt a sync and even if the sync fails due to excessive data extraction volumes, view the extraction results to determine the business components for which the data extraction was excessive. If any business component extraction is found to be excessive, you can reduce the extraction by adjusting the existing search specs specified in Siebel Tools (applets and business components), or Handheld Settings (for example, in DefaultBusObj), and selection filters (business object filters). If nothing else works, a business component filter can be used to force a reduction in the result set for a particular business component.

Setting Business Component Filters for Siebel Handheld Users

The Business Components view in the Application Administration screen contains the sync filter settings for business components. If you wish to add or remove business component filter settings for users, you do so in this view.

To add a business component filter setting

- 1 From the application-level menu, select Navigate > Site Map > Administration-Mobile > Application Administration.
- 2 In the Application Administration screen, select the appropriate application, then click the Business Component view tab.

- 3 Click New, then enter the required information.

Some fields in the Business Component view are described in the following table:

Field	Comments
Owner	Read only. Contains the Siebel Handheld application to which the business component will be associated. For example, Siebel <Application name> for CE.
Business Component	A text box. Enter the business component name.
Name	A text box. Enter the business component filter name. For example, Filter 1.
Query	A text box. Enter the syntax for the query. For example, [Start Date] <=Today() For more information on developing queries, see "Data Filtering."

To remove a business component filter setting

- 1 From the application-level menu, select Navigate > Site Map > Administration-Mobile > Application Administration.
- 2 In the Application Administration screen, select the appropriate application, then click the Business Component Filters view tab.
- 3 Select the filter setting record wish to remove.
- 4 From the Business Component Filters menu, choose Delete Record.

About Business Object Filters

The Siebel Web client supports named queries on most or all screens. These queries restrict the result set displayed to the user. Business object filters are the Handheld Sync equivalent to these named queries. Just like client based queries, they are applied to a specified business object. They also contain search or sort specifications for business components that are part of that business object.

The Default column is the only difference from the query syntax appearing in a PDQ filter for the Siebel Web client. The Default column is unique to the business object filter mechanism. For Web Client queries, users can set a default query for each view in their Preferences screen. If users do not do this, there is no default query, so all records are returned by default. This is not recommended for handheld deployments as this would result in excessive data extraction volumes. Thus, the Default column allows you to decide what filter should be used by default if a user does not make a selection. There is also a client option to revert to default filters selection. There should be at most a single default filter for each business object name. It is not recommended that you set more than one filter as the default for a particular business object. Note however, that the same default choice will be made by all clients.

Business object filters can be specified at either the Application level or the User level, but not at the Component level. Business object filters specified at the User level will override a filter specified at the application level provided the application-level filter has the identical values for the business object name and filter name. The list of filter choices presented to the user is the merged list of all application filters except those overridden at the user level, plus all user filters.

Setting Business Object Filters for Siebel Handheld Users

The Business Object Filters View in the Application Administration screen contains the sync filter settings for business objects. If you wish to add or remove business object filter settings for users, you do so in this view.

To add a business object filter setting

- 1 From the application-level menu, select **Navigate > Site Map > Administration-Mobile**.
- 2 In the Application Administration screen, select the appropriate application, and then click the **Business Object Filters** view tab.
- 3 Click **New**, and then enter the required information.
- 4 The fields in the Business Object Filters view are described in the following table:

Field	Comments
Owner	Read only. Contains the Siebel Handheld application to which the business component will be associated. For example, Siebel <Application Name> for CE.
Default	Check to allow you to decide what filter will be used by default if a user does not make a selection.
Business Object	A text box. Enter the business object name. For example, Account.
Name	A text box. Enter the business object filter name. For example, BOFilter 1.
Query	A text box. Enter the syntax for the query. For example, 'Account'.Search = "[Account Status] = LookupValue (""ACCOUNT_STATUS"", ""Active"")" 'Account'.Sort = "Name, Location". For more information on developing queries, see "Data Filtering."

To remove a business object filter setting

- 1 From the application-level menu, select **Navigate > Site Map > Administration-Mobile > Application Administration**.

- 2 In the Application Administration screen, select the appropriate application, and then click the Business Object Filters view tab.
- 3 Select the filter setting record wish to remove.
- 4 From the Business Object Filters menu, choose Delete Record.

About Thread Throttling

When a large number of users attempt to synchronize simultaneously, the load on a single server can become excessive. Thread throttling significantly reduces the total number of simultaneously active transaction processor threads and database extraction threads, thereby increasing the overall throughput for synchronization, without reducing the number of concurrent users. Synchronization performance degrades slightly but will successfully complete for all users.

Thread throttling allows the maximum possible number of concurrent users. It throttles in a manner that maximizes application server usage during any mixture of transaction processor and database extraction threads. Thus, if the server supports x concurrent transaction processing threads, it will allow this number of transaction processing threads while disallowing all database extraction threads. Similarly, if the server supports y concurrent database extraction threads, it will allow this number of database extraction threads while disallowing all transaction processing threads. If fewer than x transaction processing threads are currently active, some database extraction threads are allowed to execute concurrently. Similarly, if fewer than y database extraction threads are currently active, some transaction processing threads are allowed to execute concurrently.

For information on thread throttling settings, see [“Configuring Application Settings for Siebel Handheld” on page 54](#).

To enable thread throttling, see [“To add a new application setting” on page 58](#).

About Settings in the Handheld Administration Screens

Settings can appear at three levels: Application, Component, or User. Certain settings are only allowed at specific levels.

There are also two types of settings: single-line and multi-line settings. For a single-line setting, only one row may contain a unique setting name at a given level. Thus, a single-line setting at the User level may only be used once at that level. For single-line settings, the Sequence column should always contain a value of zero. For multi-line settings, the sequence column is necessary to allow multiple rows. The sequence column has no effect on actual processing, but is part of the logical key in the database table. When you create a new record in this database table, the record must have a unique logical key. For single-line settings, you may leave the sequence column value alone, which will result in a default value of zero being assigned. For multi-line settings, each line must include a different sequence number to avoid logical key conflicts. If the combination of setting name and sequence number is not unique for a particular parent record (Application, Component, or User), you will receive an error message when stepping off or saving the record. Multi-line entries must contain correct the key values before they can be saved to the database.

The rules for override are that any setting, whether single line or multi-line, specified at the lower levels overrides that same setting name at higher levels. Thus the settings at the application level apply unless specific settings are overridden for a particular component or a particular user. When an override occurs, it occurs for the complete setting name. Thus, if a particular multi-line setting has three rows at the user level and twelve rows at the application level, the resulting multi-line setting value for that setting will contain only the three rows at the user level. There is also an override mechanism to allow a setting to be removed, rather than replaced. To remove a setting from a higher level, specify the setting name to be removed, with an empty setting value.

Configuring Application Settings for Siebel Handheld

The Administration-Mobile screen contains a Settings list that allows you to change default settings. Some of the settings are described in [Table 10](#).

The Handheld setting value field has a limit of 2000 characters. To create a default business object (DefaultBusObj) setting value with more than 2000 characters, use the following general approach:

Break the value into multiple lines of DefaultBusObj settings. These settings should all be entered using the same DefaultBusObj value format:

- BusObj|Visibility|Query|BusComp_1|query specifications_1[|BusComp_n|query specifications_n]

When defining multiple lines of DefaultBusObj settings for a single business object, all view modes and filters should match. If a business component is found in multiple DefaultBusObj settings for a single business object, then the business component’s query specifications will be concatenated with a space and appended into the previous business component’s query specifications. You should be aware of this in order to decide if both query specifications should be combined with an OR or AND operative.

The DefaultBCuserProps and DefaultFields settings for a single business component can also be broken into multiple lines of settings if their values exceed 2000 characters. These settings should all be entered using the same value format as well:

- BusComp|BCUserProp_1[|BCUserProp_n] or BusComp|Field_1[|Field_n]

Table 10. Application Settings

Setting Name	Definition	Valid Values
AllowRememberPassword	Single-line setting. Specifies whether the Remember Password check box will be displayed on the Handheld Client Synchronization screen.	TRUE or FALSE
ApplicationDirectory	Single-line setting. Specifies the working directory (UNC path) of the Siebel Handheld synchronization component where user data are stored.	\\server name\directory name

Table 10. Application Settings

Setting Name	Definition	Valid Values
DBExtractThreadLoad	Single-line setting. Enables Thread Throttling functionality for database extract threads. It is the load (or weight) that will be assigned to each individual Database Extractor thread. For each running database extracting thread, this load value will be used to determine the total system load, which is then compared against the MaxTotalThreadLoads value. A new thread will only be started if the total system load does not exceed the MaxTotalThreadLoads value. A value of zero disables throttling of Database Extractor threads.	integer >= 0; default is 2
DefaultBCUserProps	Multi-line setting. Reduces the number of User Properties that are extracted to the device metadata, thus decreasing the number of fields for a business component that need to be extracted. These reductions lower the metadata extract size and optimize client performance by removing irrelevant user properties from the handheld configuration. If this directive is not specified for a business component, then all user properties will be extracted.	
DefaultBusObj	Multi-line setting. Used to force the extraction of a business object and its designated business components. This is typically used when a business component is not extracted because it is not specified via the "DefaultView" directive and is required for the application to function correctly. Another use of this directive is to designate business components that function as RBOs (reverse business objects).	Business Object Name Visibility Level Business Component Name QBE query construct For more on QBE (query by example) structure, see "Constructing Business Component and Business Object Filters" on page 72.

Table 10. Application Settings

Setting Name	Definition	Valid Values
DefaultFields	Multi-line setting. Used to force the extraction of fields for a particular business component. This is typically the case where the business component is extracted via the "DefaultView" directive but because the field is not visible on the applet, it is not extracted. Also when a hidden business component is extracted via the "DefaultBusObj" directive, it is necessary to specify all of the fields that need to be extracted for the business component. If no fields are specified via this directive, then the business component will not be extracted for this case.	Business Component Name Field1 Field2 ...
DefaultHandheldInsertMode	Single-line setting. Enables insert failure processing for synchronization. If enabled, synchronization will stop upon encountering a data conflict during an insert operation. End users or administrators must resolve the data conflict before synchronization can resume. This feature is disabled by default.	NoFail or FailOnError
DefaultHandheldSyncPickMode	Single-line setting. Enables Extended Pick processing for synchronization. If enabled, synchronization will stop upon encountering a data conflict during a pick operation. End users or administrators must resolve the data conflict before synchronization can resume. This feature is disabled by default.	NoFail or FailOnError
EnableBatchExtraction	Single-line setting. Enables or disables Batch Sync functionality.	TRUE or FALSE
EnableThrottleDebugMode	Single-line setting. This parameter enables or disables Thread Throttling functionality.	TRUE or FALSE
MaxThrottleWaitTime	Single-line setting. For Thread Throttling functionality. This is the upper limit on the amount of time (in minutes) any individual throttling request will be allowed to wait.	integer >= 0; default is 5

Table 10. Application Settings

Setting Name	Definition	Valid Values
MaxTotalThreadLoads	Single-line setting. For Thread Throttling functionality. It defines the maximum number of total thread loads (determined by DBExtractThreadLoad and TranProcThreadLoad for each type of thread) that will be allowed to run across the scope defined by ThreadThrottleScope. If a throttling request is made that causes this maximum to be exceeded, the requesting thread is delayed. The default value is zero, which completely disables the throttling mechanism.	integer >= 0; default is 0
NoDatabaseBusComp	Multi-line setting. Defines a business component that must be omitted from the device database and excluded from database extraction.	
NoExtractBusComp	Multi-line setting. Defines a business component that must be excluded from database extraction.	
SchemaChangeNotification	Multi-line setting. Defines a Business Service that should receive the Handheld Schema Change Notification.	(Siebel internal)
ThreadThrottleScope	Single-line setting. For Thread Throttling functionality. It defines the scope of the thread throttling mechanism as using one of two different modes: Process Thread (throttling occurs independently within each process), or Application (throttling occurs across all processes running the same handheld sync application on a single server). Only the first character of the ThreadThrottleScope parameter will be used to determine the value. All other characters are ignored. Thus "aardvark" is interpreted as "Application." Case is also ignored. The default value is "Application."	Application or Process

Table 10. Application Settings

Setting Name	Definition	Valid Values
TranProcThreadLoad	Single-line setting. For Thread Throttling functionality. It is the load (or weight) that is assigned to each individual Transaction Processor thread. For each running transaction processing thread, this load value is used to determine the total system load, which is then compared against the MaxTotalThreadLoads value. A new thread will only be started if the total system load does not exceed the MaxTotalThreadLoads value. A value of zero disables throttling of transaction processing threads.	integer >= 0; default is 3
TranProcThreshold	Single-line setting. For Thread Throttling functionality. This is the minimum time (in minutes) that the Transaction Processor will continue processing transactions before performing a handshake with the client. Once this value has been exceeded, a handshake occurs instead of starting to process the next transaction. Doing so prevents the client from timing out the session when thread throttling is enabled.	integer >= 0; default is 5
TranReapplyComponent	Single-line setting. Server component to use for playback of Companion Sync transactions for parent Companion Sync component.	
TranReapplyServer	Single-line setting. Siebel Application Server to use for playback of Companion Sync transactions for parent Companion Sync component.	

To add a new application setting

- 1 From the application-level menu, select **Navigate > Site Map > Administration-Mobile > Application Administration > Settings**.
- 2 From the Settings list menu, select **New Record**.
- 3 Click in the name field and select the desired application setting.
- 4 Click in the Value field and enter the text of the setting.

Configuring Component Level Settings for Siebel Handheld

You administer server components for your handheld device from the Administration-Mobile > Server Component screen. The component displayed is based on the application selected in the Application Administration view. The Server Component Administration screen is used for overriding application settings at the component level on a specific server. The data entered here is used by the synchronization engine when the user synchronizes with the server.

NOTE: You can use this method for Direct Server Sync but not Companion Sync.

The Server Component screen contains a list of server components associated with the application that was selected in the Application Administration screen. For each server component, the Settings view details the associated settings.

The Name field value needs to be the exact component name, such as "SalesceObjMgr_enu", of the Handheld Sync server component.

Server component settings are used primarily for functionality required for individual server components. For example, thread throttling is dependent on components running on a particular server and is best set at the server component level. Examples of settings that might be made at the component level are MaxTotalThreadLoads, TranProcThreadLoad, DBExtractThreadLoad, and so on. Generally, settings made at the application level are shared by all server components.

Administering Barcode Settings for Siebel Handheld

Siebel Handheld can scan and parse data from HIBC and UCC/EAN barcodes. Siebel Administrators can set up Siebel Handheld to scan and parse any one-dimensional barcode and render the corresponding data in an applet. For example, if a control in a list applet is enabled for barcode scanning and the barcode scanned is valid, the handheld application will parse the barcode, create a new record, and fill in the field with parsed data. In form applets, after the user scans an item, the data representing the item automatically populates the barcode-enabled field. In order to do this, Siebel Administrators must define the barcodes and how data will be parsed from these barcodes in the Barcode Administration view.

Enabling Barcode Scanning in Siebel Handheld

Before using the barcode scanning feature, you must add the following parameter value in setup.ini:

```
EnableBarcode = Y
```

NOTE: In the event that your handheld application is not preconfigured to enable barcode scanning, you must make an Application Event Services entry in Siebel Tools.

To enable barcode scanning

- 1 Navigate to Application object, and then select Siebel Sales for CE.
- 2 Expand to Application Event Services object, add a new entry with the following:

Name: SHCE Core Barcode Service
Event Name: HHCE_Start
Business Service: SHCE Core Barcode Service

Mapping a Button for Socket In-Hand Scan Card

Siebel Handheld applications support embedded barcode scanners provided in Symbol and Intermec devices. In addition, Siebel Handheld applications support certain Socket scan cards. See *System Requirements and Supported Platforms* on Siebel SupportWeb for a list of supported handheld devices and Socket scan cards. Note that different Socket scan cards will require different scan card driver programs to be installed. Check with the card vendors/websites for required driver program installation.

For Intermec and Symbol devices, the barcode scanning can be triggered by the built-in buttons. If you are using Socket scan cards, the following steps are required to be taken on the Handheld device for mapping a button to the barcode-triggering utility software, SocketTrigger.exe.

To map a button to SocketTrigger.exe (Socket Scan Card only)

- 1 Navigate to Start > Settings > Personal > Buttons.
- 2 From the Button list, select a button to trigger In-Hand Scan Card.
- 3 In the Button Assignment field, select SocketTrigger, and then tap OK.

Creating New Barcode Definitions for the Handheld Application

You can define new one-dimensional barcodes in the Barcode Administration views. To define a new barcode, you need to create a new barcode definition in the Barcodes list, then create corresponding records in the Barcode Item list to define data elements within the barcode.

To create a new barcode definition

- 1 From the application-level menu, select Navigate > Site Map > Administration-Mobile > Barcode Administration.

- 2 Click New, then fill in the fields.

The fields in the Barcodes list are described in the following table:

Field	Comments
Name	Required. Any descriptive name for the barcode. Must be unique for all records defined in the Barcode screen.
Sequence	Required. This is the sequence for barcode parsing. The lower of two sequence numbers takes precedence when deciding which barcode in the list to match. For example, if a scanned barcode matches two entries in the barcode list, the one with a lower sequence number will be picked for the match. The lowest sequence number is 1.
Barcode Type	Required. Type of barcode standard. Can either be Location or Code. For a Location type barcode, the barcode data element parsing is done solely by the Sequence field in Barcode Item list. For a Code type barcode, the barcode data is first parsed into multiple sections by the Code field in the Barcode Item list, then is further parsed by the Sequence field for each section. See "Example of Location Type Barcode" on page 63 and "Example of Code Type Barcode" on page 64 .
Buscomp	Optional. Used to designate into which business component the target data is placed.
Min Length	Optional. The minimum length for the barcode data in digits. If it is not set, the default minimum length is 1.
Max Length	Optional. The maximum length for the barcode data in digits. If it is not set, the default maximum length is 10000.
Prefix	Optional. Defines the value that the parsing algorithm uses to identify barcode definition to use. The allowed format for Prefix is any ASCII character for exact match, '#' for any single digit number match (that is, 0 - 9), '&' for any alphabet character in lower and upper case, or '*' for a wild card match. For example, you can enter ##9&* as the prefix, which means the first two characters can be any number, the third character has to be '9', the fourth character can be any alphabet character, and the fifth character can be any ASCII character.
Suffix	Optional. Allows you to associate suffixes with individual fields. The allowed format for Suffix is the same as the one specified for Prefix. In addition, the rules for matching Suffix are the same as the ones for Prefix.
Description	Optional. Detailed description for this barcode.

- 3 In the Barcode Item list, add new records to identify how data will be parsed from barcode.
Depending on the type of barcode standard you just defined (either Location or Code), you then need to create new records in the Barcode Item list to identify how data is parsed.
- 4 In the Barcode Item list, Click New, then update the required fields.
Some of the fields are described in the following table:

Field	Comments
Name	Required. Name of the barcode item (for example, Product Name corresponds to the Product Name field). This name does not determine which field in BusComp the parsed data is written to. That field is determined by the "Data Desc" field.
Code	Applicable for Code barcodes only. Used to break a barcode into multiple barcode sections.
Sequence	Required. The sequence for barcode data elements parsing. For Location barcodes, this corresponds to the sequence used to parse data elements from the barcodes. For Code barcodes, this corresponds to the sequence used to parse data elements within barcode sections.
Min Length	Required. Minimum Length of the character string for this data element. If this is a variable length string, then Minimum Length is not equal to Maximum Length.
Max Length	Required. Maximum Length of the character string for this data element. If this is a variable length string, then Minimum Length is not equal to Maximum Length.
Data Desc	Optional. Used by algorithm to identify what field to parse this data into. For example, Product Name corresponds to the Product Name field.
Data Format	Optional. Defines format for data element (for example, MMDDYY is for date).
Action	Optional. Defines the action for the data element. Both Data Format and Action are written to the field specified in "Data Desc" by the following format: "<parsed data element>,<Data Format>,<Action>". See the example in Table 14 .

Example of Location Type Barcode

The two entries for the Barcode list, HIBC Secondary and IBM, are shown in [Table 11](#).

Table 11. Location Type Barcode List Entries

Name	Sequence	Barcode Type	Buscmp	Min Length	Max Length	Prefix	Suffix	Description
HIBC Secondary	1	Location	Medical Product		31	+\$9###3		
IBM	2	Location	Tech Product		30	+\$9###39		

Entries for Barcode - HIBC Secondary in the Barcode Item list are shown in [Table 12](#).

Table 12. Location Type Barcode Item List Entries

Name	Code	Sequence	Min Length	Max Length	Data Desc	Data Format	Action
Prefix		1	4	4	Prefix		
Quantity		2	5	5	Quantity		
Exp date flag		3	1	1	Exp flag		
Date		4	6	6	Expiration Date	YYMMDD	
Lot		5	0	13	Lot #		
Link		6	1	1	Link		
Check		7	1	1	Check		

If the barcode being scanned is +\$90010039509283C001LZ, both barcode entries "HIBC Secondary" and "IBM" are good matches. Since HIBC Secondary has a lower sequence as 1, it is picked as the final match for parsing the barcode. The data is parsed as follows:

{(Prefix, "+\$9") (Quantity, "00100") (Exp flag, "3") (Expiration Date, "950928,YYMMDD") (Lot #, "3C001") (Link, "L") (Check, "Z")}

NOTE: In this example, the use of "Prefix" in the two tables is different. The Prefix column in the Barcode list table is required for matching the record in the Barcode list. The Prefix row in the Barcode Item list table is a user-defined data element to be parsed for a particular barcode.

Example of Code Type Barcode

Entries for Code type barcode in the Barcode list are shown in [Table 13](#).

Table 13. Code Type Barcode List Entries

Name	Sequence	Barcode Type	Buscomp	Min Length	Max Length	Prefix	Suffix	Description
UCC/EAN	1	Code	Medical Product		37	01		

Entries for Code type barcode in the Barcode Item list are shown in [Table 14](#).

Table 14. Code Type Barcode Item List Entries

Name	Code	Sequence	Min Length	Max Length	Data Desc	Data Format	Action
AI 01	01	1	2	2	AI 01		
Packaging Indicator	01	2	1	1	Indicator		
UCC/EAN #	01	3	12	12	UCC/EAN		
Link	01	4	1	1	Link		
Quantity Section	30	1	3	5	Quantity Section	1000	Validate
AI 240	240	1	3	3			
Product #	240	2	1	13	Product #		

The barcode UCC/EAN is parsed to three sections, 01, 30, and 240. If the barcode being scanned is **01103123456789033050240**ABCDEFGF, the data is parsed as follows:

Parsed Data = {(AI 01, "01") (Indicator, "1") (UCC/EAN, "031234567890") (Link, "3") (Quantity section, "3050,1000,Validate") (Product #, "ABCDEFGF")}

NOTE: The Code portions in the barcode appear in bold text.

Enabling Applications Views for Barcode Scanning

You can enable any existing or new view for barcode scanning.

To enable an application view for barcode scanning

- 1 From the application-level menu, select Navigate > Site Map > Administration-Mobile > Barcode Enabling.
- 2 Click New, then enter the necessary information.

The fields in the Barcodes list are described in the following table:

Field	Comments
View	The view in the handheld application from which the scan occurs.
Applet	The applet within the view from which the scan occurs.
Buscomp	The business component from which information is drawn.
Buscomp Field	The specific field within the business component that should be updated through barcode scanning.

Example: Process of Creating a New Barcode Definition in the Service Handheld Application

Although this example is for the Siebel Service Handheld device, it pertains to all Siebel Handheld products. You can define new one-dimensional barcodes in the Barcode Administration views. To define a new barcode, you need to create a new barcode definition in the Barcode list, then create corresponding records in the Barcode Item list to define data elements within the barcode.

To create a new barcode definition, complete the following procedures:

- [“To create a new barcode definition for Siebel Service Handheld” on page 65](#)
- [“To enable the SHCE Service FS Activity Parts Movements views for barcode scanning” on page 66](#)

To create a new barcode definition for Siebel Service Handheld

- 1 From the application level menu, select Navigate > Site Map > Administration-Mobile > Barcode Administration.
- 2 Click New, then fill in the necessary fields.

The following table describes the fields in the Barcodes list.

Field	Sample Data
Name	Hard Disk 100 GB
Sequence	Set to the greatest number in the current list view plus one
Barcode Type	Location
Buscomp	FS Activity Parts Movement

Field	Sample Data
Min Length	12
Max Length	12
Prefix	#
Description	Service

- 3 In the Barcode Item list, add a new record to identify how data will be parsed from the barcode. The following table describes the fields in the Barcode Item list.

Name	Sequence	Min Length	Max Length	Data Desc
UPC Code	1	1	1	
MFG Code	2	5	5	
Product Name	3	5	5	Product Name
CC	4	1	1	

NOTE: Reducing the amount of barcode seed data extracted to the Service Handheld application improves client performance and reduces synchronization database extract size. The following steps provide an example of extracting only the barcode standards that are required for the Service Handheld application. This is applicable as long as all the barcode records for the Service Handheld application defined in the Barcode list have the Description attribute set to "Service."

- 4 From the application level menu, select Navigate > Site Map > Administration-Mobile > Application Administration.
- 5 In the Application Administration view, select "Siebel Service for CE."
- 6 Click the Settings view tab, and make sure the parent record is the application "Siebel Service for CE."
- 7 Locate the "DefaultBusObj" directive that has the following value:
 - "SHCE Barcode|0||SHCE Barcode||SHCE Barcode Item||SHCE Barcode Enable|".
 Replace that value with the following value:
 - "SHCE Barcode|0||SHCE Barcode|[Description]="Service"|SHCE Barcode Item||SHCE Barcode Enable|".

To enable the SHCE Service FS Activity Parts Movements views for barcode scanning

- 1 From the application-level menu, select Navigate > Site Map > Administration - Mobile > Barcode Enabling.
The Barcode Enable list appears.

- 2 If the following record does not exist, create a new record to enable the Product Name field in the SHCE Service FS Activity Part Movements List Applet for barcode scanning with the following information:

View	Applet	Buscomp	Buscomp Field
SHCE Service FS Activity Part Movements	SHCE Service FS Activity Part Movements List Applet	FS Activity Parts Movement	Product Name

- 3 If the following record does not exist, create a new record for the Product Name field in the SHCE Service FS Activity Part Movements Form Applet for barcode scanning with the following information:

View	Applet	Buscomp	Buscomp Field
SHCE Service FS Activity Part Movements (More Info)	SHCE Service FS Activity Part Movements Form Applet	FS Activity Parts Movement	Product Name

- 4 Save the changes. Now the Buscomp Field "Product Name" in both the "SHCE Service FS Activity Part Movements" view and the "SHCE Service FS Activity Part Movements (More Info)" view have been enabled for barcode scanning. The Buscomp Field "Product Name" specified here matches the value in the Data Desc column in the Barcode Item list defined earlier.

NOTE: The example provided above assumes that the product Hard Disk 100GB has been defined and properly set in the appropriate product catalog.

About Monitoring Synchronization Sessions for Siebel Handheld

You monitor Siebel Handheld application synchronization sessions and synchronization conflicts from a number of screens within the Siebel Mobile Web Client, or if you are using DSS or DSSvP you do so by way of the Siebel Web Client. Every time a user synchronizes with the server, a record is made.

The following topics relate to synchronization monitoring.

- ["Monitoring Synchronization Sessions for Siebel Handheld" on page 68](#)
- ["Obtaining Error Details from Siebel Handheld Synchronization Sessions" on page 68](#)
- ["Obtaining Business Component Information from Siebel Handheld Synchronization Conflicts" on page 69](#)

- [“Obtaining an Audit Trail for Siebel Handheld Synchronization Sessions” on page 69](#)
- [“Acting Upon Synchronization Errors in Siebel Handheld” on page 70](#)

Monitoring Synchronization Sessions for Siebel Handheld

The Session Administration view allows you to gather all data related to each sync session a user performs. The Sync Status list appears above two child lists: Sync Sessions and Extraction Info. These lists allow you to do the following:

- **Sync Status:** Allows you to monitor each user sync session, and includes such data as: sync status, the date, type of sync and so on.
- **Sync Sessions:** Allows you to gather further information on the status of each sync session, including conflicts during the sync, the size of the data extracted, and so on.
- **Extraction Info:** Allows you a detailed look at all data extracted during the sync session, including business component information, the number of records extracted. You use this list to help get answers to questions such as the following:
 - Why did a particular record download to the device?
 - Why is an expected server record not downloaded to the device?
 - Why is the total number of records showing up in some view so big?
 - Why is the total number of records showing up in some view so small?
 - Why does the extraction take so long?

There is one extraction record for each unique extraction context. The extraction record will list the filters used to control the extraction, the context of the extraction, how many records exist in that context for those filters, and how long it took to extract that set of records. By analyzing these records, and looking at all extraction changes resulting from filter changes, and, or changes to search specs (defined in Siebel Tools), you can answer all of the above questions.

To monitor synchronization sessions

- From the application-level menu, select **Navigate > Site Map > Administration-Mobile > Session Administration**.

The Sync Status list appears, with the two child lists, Sync Sessions and Extraction Info, below it.

Obtaining Error Details from Siebel Handheld Synchronization Sessions

The Conflict Administration view allows you to obtain details of sync errors that occur during individual sync sessions.

To obtain synchronization error details

- 1** From the application-level menu, select Navigate > Site Map > Administration-Mobile > Conflict Administration.
- 2** In the Transactions list, select the appropriate record, and then click the Error Details view tab.
- 3** In the Error Details list, select or query for the desired record.

Obtaining Business Component Information from Siebel Handheld Synchronization Conflicts

The Transactions view on the Conflict Administration screen allows you to obtain business component information related to synchronization errors that occur during individual sync sessions.

To obtain business component error details

- 1** From the application-level menu, select Navigate > Site Map > Administration-Mobile > Conflict Administration.

The Transactions view appears.

- 2** In the Transactions view, select the appropriate record, and then click the Business Components view tab.

Obtaining an Audit Trail for Siebel Handheld Synchronization Sessions

The Transactions view on the Conflict Administration screen allows you to obtain audit trail information for an action that was taken against a particular transaction.

NOTE: You must enable Audit Trail separately. For information on enabling Audit Trail, see *Applications Administration Guide*.

To obtain audit trail information for synchronization error details

- 1** From the application-level menu, select Navigate > Site Map > Administration-Mobile > Conflict Administration.

The Transactions view appears.

- 2** In the Transactions view, select the appropriate record, and then click the Audit view tab.

Acting Upon Synchronization Errors in Siebel Handheld

Upon reviewing a synchronization error, you can act upon it by performing one of three different actions.

To act upon handheld sync transaction errors

- 1 From the application-level menu, select Navigate > Site Map > Administration-Mobile > Conflict Administration.

The Transactions list appears. The transaction buttons are described in the following table:

Action	Result
Reapply	<p>Reapplies the selected transaction with values listed in the view (or Field Value view). These values override the results provided by the server.</p> <p>TranReapplyComponent and TranReapplyServer are necessary when using Companion Sync and ignored for Direct Server Sync. These are used when selecting transactions to reapply from the Administration - Conflict screen.</p> <p>If TranReapplyComponent and TranReapplyServer are not specified, it is impossible to reapply transactions originating from Companion Sync.</p>
Export	Exports the content of the transaction in the same format used by the sync engine. This output file can be sent to Siebel Technical Support for problem analysis.
Ignore	Accepts the current status and does not act upon the error. The record becomes read-only. There is no impact, except that the error will no longer appear in queries for unresolved conflicts.

- 2 Click either Reapply, Export, or Ignore depending on your needs.

5

Data Filtering

The following topics are covered in this chapter:

- [“Developing Data Filters for Handheld” on page 71](#)
- [“Constructing Business Component and Business Object Filters” on page 72](#)
- [“Business Object Filters” on page 73](#)
- [“Recommendations for Managing Handheld Business Object Filters” on page 73](#)
- [“Examples of Default Business Object Declarations” on page 74](#)

Developing Data Filters for Handheld

The following general steps are recommended for developing Handheld synchronization filters.

- Identify the screens and views of your application. Then identify the business components that are required to support each screen and view, noting the areas where each business component occurs. For example, identify the form, list, or pick applets that are based on each business component.
- Within Siebel Tools, establish the base parent-child relationships and any reverse relationships at the component level.
- Review the business components that occur in picklists and consider creating business component filters for those that will cause large numbers of records to synchronize to the device. These filters are created and maintained in the Mobile Administration screens. For each business component, determine whether it is possible to apply a search specification to all instances of the business component within the Siebel Handheld application. Develop a set of suitable business component filters in the Mobile Administration screens.

Common examples of business components that are suitable for global business component filters include:

- Employees (for large organizations)
 - Activities (for example, filter for current Activities, Activities of only certain kinds)
 - Accounts (for example, by geography)
 - Products (for example, active, orderable products)
 - Orders (for example, open, closed in last three months)
- Create appropriate business object synchronization filters for each business object and make sure that each business object includes a default filter. Default filters make sure that users avoid accidental download of an excessive number of records.

Constructing Business Component and Business Object Filters

Business component filters are used to limit the extraction of a business component for every context in which it is extracted.

Example of Business Component Filter Syntax:

Business component filters use query by example (QBE) syntax.

```
[Status] = "Not Started" OR [Status] = "In Progress" OR ([Status] IS NULL) OR [Status] = "On Hold" OR ([Status] = "Done" AND [Done] >= Today() - 7)
```

For more information on QBE syntax, see *Siebel Developer's Reference*.

Business object filters are used to supply filters that a user can select at sync time. These are the filters that are displayed in the SetFilters dialog on the device.

Example of Business Object Filter Syntax:

Business object filters use predefined query (PDQ) syntax.

PDQ syntax rules are as follows:

- The business component name should be a valid business component in the business object on which the PDQ is based
- Search and Sort can be specified for all active buscomps in the business object on which the view is based, appended to each other in any order using space as delimiter.

The normal search spec and sort spec syntax applies except that quotes in the search spec have to be escaped using double quotes since the search spec itself is enclosed in double quotes.

The syntax is as follows. Descriptions of the terms are shown in [Table 15](#).

```
'Account'.Search = "[State] = LookupValue ( ""STATE_ABBREV"", ""CA"" )" 'Account'.Sort = "Name, Location"
```

Table 15. Business Object Filter Syntax

Syntax Term	Description
Account	business component name
Search	key word
"[State] = LookupValue (""STATE_ABBREV"", ""CA"")"	search specs using PDQ syntax
State	field name
LookupValue	function for find an LOV value
STATE_ABBREV	LOV type
CA	LOV value
'Account'.Sort = "Name, Location"	sort spec for sorting the returned list

For more information on PDQ syntax, see *Siebel Developer's Reference*.

Business Object Filters

All Siebel Handheld business object filters are available for selection by a user at the time of sync. Additionally, there is no naming convention for business object filters.

A default filter for a business object is indicated by checking the Default flag in the Administration-Mobile > Application Administration > Business Object Filters view of the Siebel Web client. Be sure to define a default filter for each business object in the Siebel Handheld application. If no filters are applied during the synchronization process, an unacceptably high volume of data will be downloaded to the handheld device.

CAUTION: You should select only one filter as the default for each business object. If two filters are marked as the default for the same business object, the actual default can be determined only by attempting to sync and selecting default filters from the sync client filter selection UI.

Recommendations for Managing Handheld Business Object Filters

The following section provides recommendations for creating and managing filters according to synchronization methods.

Companion Sync Deployments

Administrators typically provide their users with an initial set of Handheld business object filters and instruct them how to manage the synchronization filters themselves later. They are maintained in the Administration-Mobile > Application Administration > Business Object Filters view. This view is hidden from mobile users so they cannot create their own business object filters.

You manage these filters at the server level, then replicate any updates you make down to the companion computers via Siebel Remote. The Handheld user can then access the updated filters after performing a Companion Sync operation. For more information, see ["Setting Business Object Filters for Siebel Handheld Users" on page 52](#).

Additionally, there are several sample Handheld business object filters in the sample database, as well as in the Siebel 7.8 seed data.

Direct Server Sync Deployments

For Direct Server Sync deployments, administrators can create user-specific business object and business component filters in the Administration-Mobile > User Administration view. For more information, see ["Setting Business Component Filters for Siebel Handheld Users" on page 50](#) and ["Setting Business Object Filters for Siebel Handheld Users" on page 52](#).

Both application-level and user-level filters can be used in this deployment. They are managed in the same set of views. Changes to any filters will be effective on your next sync session, without having to restart the Handheld synchronization OM component.

These business object filters are made available to all end users and, therefore, must be defined with the needs of all end users in mind.

Examples of Default Business Object Declarations

You can set default business object declarations in the Administration-Mobile > Application Administration > Settings screen, as described in the following examples.

Example 1

"State Model" default business object setting:

```
State Model - Engine|0||State Model|[BusComp Name]="Expense"|State Model -  
Transition||State Model - State||State Model - Position|
```

The first three segments of the declaration are followed by a series of repeating BusCompName Search Spec pairs:

- 1 Business object name
 - 2 Visibility Type
 - 3 (Siebel internal)
 - 4 Root business component name
 - 5 Search spec QBE for root BusComp records
 - 6 Child business component name
 - 7 Search spec QBE for child BusComp records (this should normally be empty, causing all children to be extracted)
 - 8 Grandchild business component name
 - 9 Search spec QBE for grandchild BusComp records (this should normally be empty, causing all grandchildren to be extracted)
- and so on

The total number of fields must be at least 5 and must be an odd number.

Example 2

```
Action|0||Action||Action Employee|
```

This example default business object declaration results in an extraction of the Action and Action Employee business components where they occur with visibility 0 using the business object filter indicated. The business object filters are generally used only for extracting business components that do not correspond to any views or applets. Business object declarations identify specific business components within the business object to be extracted. The business object filters normally give a query based on the primary business component in the business object and force extraction of any business components mentioned in the query when there is no corresponding applet within the application that can cause the desired extraction to occur.

Example 3

In the following example, the declaration is used to extract all the Price List Line Items under the Order Entry (Sales) business object.

```
DefaultBusObjs13= Order Entry (Sales)|0||Price List Item|
```

Note that this declaration lacks an associated QBE clause. When this is the case, all of the records available to the user for the given visibility are extracted.

Exercise caution when modifying a default business object setting for pick applets, and do so only with the support of a skilled Siebel configurator.

Use default business object declarations to force the extraction of data for a given business component in the context of a given business object and Visibility type. For more information on visibility designations, see ["Designating Visibility" on page 75](#). The default business object extractions are performed in the first phase of data extraction.

You will most often use these declarations to extract additional data that is not extracted as part of the user interface extraction. This may be useful for business components that are referenced programmatically by other business components, but are not exposed in the user interface. The default business object declarations are used to enforce the extraction of a subset of data to the handheld that would not have been otherwise extracted or, most commonly, to filter the data downloaded for dynamic picklists or pick applets.

All pick data is not downloaded to the device due to the memory constraints on the device. Only pick data for fields that are editable is downloaded. Therefore, if you are doing a query on a pick field, you may not be able to display the picklist. When viewing a record in an applet, if a pick field is read-only, its pick button will be disabled. If end users select a read-only field with a pick control, they receive the following error: "No data available in picklist because field is read-only."

Designating Visibility

It is very important that you use the correct visibility designation in the default business object declarations. The visibility entered should be the visibility that governs the data displayed for the business component within the context of the business object specified in the declaration. In the previous Example 1, visibility code 3 is designated. This corresponds to All Visibility, which is the visibility that applies to the Account business component when it is used in a pick applet.

You determine the correct visibility to use by examining View and business component properties within Siebel Tools. When creating a default business object declaration to restrict the volume of data extracted for a pick applet, begin by examining the Popup Visibility Type in Business Component Properties. Cross-reference the visibility type to the list below, and enter the appropriate visibility code in the declaration. If the Popup Visibility Type field on the business component is null, the default value is All. [Table 16](#) summarizes popup visibility types and the corresponding visibility codes.

Table 16. Visibility Codes

Popup Visibility Type	Visibility Codes
Sales Representative	0
Manager	1
Personal	2
All	3
None	4
Organization	5
Contact	6

NOTE: Do not use the Group, Catalog, or Sub Organization Popup Visibility Types. These are not supported in the CE handheld applications.

Overriding the Popup Visibility

If the Popup Visibility Type setting is not sufficiently restrictive (for example, All Visibility), this can lead to a large number of records being extracted when the picklist is processed during synchronization. Making the Popup Visibility Type more restrictive reduces the number of records extracted for picklists. The `OverridePopupVisibility` user property for an applet overrides the Popup Visibility Type on a business component. Use this property when the desired visibility differs from the business component's Popup Visibility Type, and you do not want to change the Popup Visibility Type. If several picklists use the same business component, you can also use the `OverridePopupVisibility` user property to vary the visibility of the picklists in the different applets.

There are two considerations you should keep in mind if multiple applications are sharing the same repository. First, changing the Popup Visibility Type has a global effect for all instances where the business component is used. If multiple applications share the same repository and use the same business components, changing the Popup Visibility Type for a common business component could have an undesirable effect for another application. Second, if multiple applications share the same applet, the picklist in each applet shares the same visibility as defined by `OverridePopupVisibility` property. This is because the `OverridePopupVisibility` property is set on the containing applet.

In Siebel Tools, navigate to Applet > Applet User Properties, and define the OverridePopupVisibility user property on the applet containing the control that opens the pick applet. See Table 17 for a description of the syntax. Assign a value to this property using the syntax shown, where <buscomp field n> is the underlying business component field of an applet control or column, and <visibility type> is the code corresponding to the desired visibility of the picklist’s business component. (See Table 16 for a list of the visibility codes.) Because the name of the OverridePopupVisibility parameter must be unique, append a unique number to the name of the parameter for any other picklists, for example, OverridePopupVisibility1, OverridePopupVisibility2, and so on.

Table 17. OverridePopupVisibility Syntax

Name	Value
OverridePopupVisibility	<buscomp field 1>, <visibility type>
OverridePopupVisibility1	<buscomp field 2>, <visibility type>
OverridePopupVisibility<n>	<buscomp field n + 1>, <visibility type>

NOTE: If OverridePopupVisibility is used, then the picklist and pick applet search specifications are ignored during synchronization when the records for the picklist are extracted.

6

Deployment of Siebel Handheld

This chapter includes the following topics:

- [“Overview of Server Installation in Support of the Siebel Handheld Client” on page 79](#)
- [“Process of Server Installation for Siebel Handheld Direct Server Sync” on page 81](#)
- [“About Siebel Handheld Synchronization Performance and Scalability” on page 84](#)
- [“Process of Installing the Siebel Handheld Application” on page 86](#)
- [“Installing Print Templates in the Siebel Handheld Install Directory” on page 91](#)
- [“Setting Up Siebel Handheld Application Installation on a CompactFlash Card” on page 91](#)
- [“Changing the SyncURL on Siebel Handheld Devices” on page 92](#)
- [“Installing the Siebel Handheld Application from External Media” on page 92](#)

Overview of Server Installation in Support of the Siebel Handheld Client

This section provides an overview of important factors to consider when planning Direct Server Synchronization (DSS) infrastructure. One aspect of successful planning and execution of a Siebel Handheld DSS deployment is to understand hardware and network requirements. While these factors are generally applicable to all deployments, there are unique aspects to each customer configuration and implementation strategy. Therefore, it is highly recommended that customers conduct detailed configuration, sizing, and production readiness reviews with Siebel Expert Services. This is especially important for complex deployments, such as those supporting large numbers of users over wide geographic areas.

You can also improve the performance and scalability of DSS deployments by working with the Siebel application server component parameters. For more information about the Siebel application server, see [“Optimizing Server Process Management for Direct Server Sync” on page 84](#).

NOTE: The recommendations in this chapter are general ones and are intended to raise your awareness of the key factors in handheld synchronization, performance, and scalability. These factors must be confirmed for your actual environment, and the usage patterns in your enterprise should be taken into consideration.

Server Topology Overview

The diagram in [Figure 1](#) shows the servers and components that are required to deploy Direct Server Sync. The components are the Siebel database, Siebel server, Siebel Web engine, and Siebel Handheld. The synchronization components are the Siebel Sync Engine which resides on Siebel server and the Sync client on Siebel Handheld.

CAUTION: Companion Sync uses Siebel Remote to complete the synchronization process to the Siebel server from the laptop. The remote mobile user's routing model must be set to Handheld User. Otherwise, sync will fail. For more information, see *Siebel Remote and Replication Manager Administration Guide*.




Figure 1. DSS Servers and Components

Recommended Hardware and Network Configuration

There are many factors to take into account when designing and implementing your server and network hardware and architecture, and sizing your database. The critical factor in sizing a handheld implementation is the expected peak synchronization load. Specific application variables to consider in calculating this load are: the number of concurrent users, number of transactions, and size of the data file. These variables should be considered within the context of the hardware specifications, including memory and processor speed.

The following resources are available as you plan your Siebel Handheld implementation:

- Refer to Microsoft and manufacturer documentation for comprehensive information on server hardware and registry parameters.
- Refer to Siebel Technical Note 405 for specific recommendations on the following topics:
 - Server Architecture
 - Server Hardware and Registry Parameters
 - Database Server Sizing
 - Database Tuning
 - Dial-Up and Network
 - Wireless
 - VPN (Virtual Private Networks)

- The Expert Services Handheld Review Package assists customers with planning their hardware and network for handheld implementations. Contact Siebel Expert Services for more information about this program.

Process of Server Installation for Siebel Handheld Direct Server Sync

The server components that are required for Siebel Handheld are installed when you install the Siebel server. See the Siebel Server installation guide for your operating system for details on installing and configuring Siebel server. The Siebel server installer copies the necessary DLLs to create an Object Manager for Direct Server Sync and creates and configures a Server Component and Component Group. The rest of this subsection describes which options you must select to correctly install the software, along with creating or configuring additional Object Managers.

This process includes the following tasks:

- [“Installing the Direct Server Sync Components Using the Siebel Server Installer” on page 81](#)
- [“Configuring Direct Server Sync Logging Levels” on page 82](#)
- [“Optimizing Server Process Management for Direct Server Sync” on page 84](#)

Installing the Direct Server Sync Components Using the Siebel Server Installer

Install the Siebel server, following the instructions in the Siebel server installation guide for the operating system you are using. When you reach the Setup Type screen in the Installer wizard, you are presented with three installation options:

- **Typical.** This setup option installs all Siebel server components except those displayed.
- **Compact.** This setup option installs only those components necessary to run the Siebel server, but no additional components or help.
- **Custom.** This setup option lets you customize your installation by choosing the specific components you want to install.

To install the Direct Server Sync components with your Siebel Server installation

- 1 During the Siebel Server installation, when the Setup Type screen appears, choose the Custom setting, and then click Next.

NOTE: At this screen, you may also choose a different directory for your Siebel server installation.

- 2 From the following components, choose Handheld Synchronization:

- Object Manager Component
- Handheld Synchronization
- Siebel Data Quality Connector

- Remote Search Support
- Siebel Java Integrator

NOTE: You must enable Handheld Synchronization to enable Direct Server Sync for your DSS installation.

3 Click Next.

Continue with the installation in *Siebel Installation Guide for Microsoft Windows: Servers, Mobile Web Clients, Tools*.

The install wizard automatically installs and configures the DSS components.

DSS Server Component Parameters

See [Table 18](#) for a list of required parameters. For information on adding DSS server components, see *Siebel System Administration Guide*.

Table 18. DSS Server Component Parameters

Parameter	Default Value	Description
ApplicationName	SiebelSales for CE	The Siebel Handheld application. This value must match the name of the application as it is specified in Siebel Tools.
ApplicationTitle	Siebel Sales	The name of the Siebel Handheld application as shown on the title bar on the browser. This parameter is only used if the Siebel application developed for the handheld is run on the Web client.
ApplicationSplashText	Siebel Sales	The Siebel Handheld application name as shown on the splash screen. This parameter is only used if the Siebel Tools application developed for the handheld is run on the Web client.
ComponentName	Siebel Sales Client	Required for Direct Server Sync, it is entered in the registry on the handheld device.

Configuring Direct Server Sync Logging Levels

To set the logging level, you need to perform the following two tasks:

- ["To configure server logging levels" on page 83](#)
- ["To configure server logging levels using the Server Configuration screen" on page 83](#)

You set the logging level to a value between 1 and 5 as shown in [Table 19](#).

Table 19. Direct Server Sync Logging Levels

Logging Level	Results
1	Error listing
2	Warning listing
3	Information listing, including SQL tracing
4	Information listing
5	Debug

To configure server logging levels

- 1** Log into Server Manager from a (m:\siebel\bin\w32ud) prompt.
- 2** Run the following:

```
change evtloglvl HandheldSyncLog=[LogLevel] for comp [OMName], where [LogLevel] = an integer between 1 - 5 (5 enables all logging) and [OMName] = the OM name (for example, <ApplicationName>CEObjMgr_enu).
```

To configure server logging levels using the Server Configuration screen

- 1** Navigate to Administration - Server Configuration > Servers > Components.
- 2** In the Component list, query for the appropriate component, such as Handheld Sales CE (ENU).
- 3** In the Events list, search for the event type Handheld Sync Logging.
- 4** Set the value to a number between 1-5 and then save the change.
 See [Table 19](#) for logging level results.

Configuring Companion Sync Logging Levels

To enable logging for Companion Sync process, you must add a parameter to the [pda] section of the CFG file.

To configure Companion Sync logging levels

- 1** Navigate to \client\bin\enu (or other language directory, such as \client\bin\fra).
- 2** Add the parameter HandheldSyncLogLevel and a valid value (1-5) to:

```
salesce.cfg (Sales Handheld) or siasalesce.cfg (SIA Sales Handheld). For example, HandheldSyncLogLevel = 5.
```

 See [Table 19](#) for logging level results.

Optimizing Server Process Management for Direct Server Sync

Several parameters are outlined below that help optimize server processing for Direct Server Sync.

To set parameters to optimize server process management

- 1 Log into the Siebel client as a user with Administrative responsibility.
- 2 Navigate to Site Map > Administration - Server Configuration > Servers > Components > Parameters.
- 3 In the Component Parameters sub-view, query for SalesCEObjManager.
- 4 Use the following table to update the parameters.

Parameter	Description
Max Tasks	Determines the maximum number of threads that can run concurrently for a given component. You should set the value of this parameter to a number equal to that of the expected peak number of concurrent synchronizations.
Min MT Servers	Determines how many multithreaded server processes are started by default for the Siebel Object Manager.
Max MT Servers	Defines the maximum number of processes supported by the instance of the Siebel Object Manager. The value for this parameter should be the same as Min MT servers and should be set so that threads per process (Max Tasks/Max MT Servers) is optimized.

About Siebel Handheld Synchronization Performance and Scalability

There are a number of factors that affect the performance and scalability of handheld synchronization. It is very important that administrators and those involved in the design and deployment of Siebel Handheld understand the impact of usage parameters on synchronization performance and scalability. For more information, see Technical Note 405 for application-specific variables affecting synchronization and data from synchronization scalability tests.

Using Multiple Synchronization Servers

As you scale your deployment, you may need to use multiple synchronization servers to accommodate all of your users. Your end users must be manually assigned to a particular server. Resonate products cannot be used for load balancing. Refer to Technical Note 405 and to your hardware manufacturer's documentation for more information on scaling deployments.

Providing Synchronization Security with Secure Sockets Layer

The synchronization data stream can be secured using Secure Sockets Layer (SSL). To employ SSL security:

- Make sure that a certificate has been created and installed on all Web servers that service handheld synchronization.

Use the following steps to install the root certificate on each handheld device.

To install the root certificate on the handheld device running PPC 2003 or newer

- 1 Navigate to the certificate authority server from your desktop computer.
- 2 Select the first option (retrieve the CA certificate or certificate revocation list), and click Next.
- 3 Click on Download CA certificate.
- 4 Click Save, and save as certca.cer on your desktop.
- 5 Use ActiveSync to copy the downloaded certificate, certca.cer, from the desktop to the My Documents folder on the handheld device.

NOTE: Make sure the certca.cer file is copied into the My Documents folder.

- 6 Go to My Documents and tap the certificate icon.

The certificate should be installed. You can validate it by going to Settings > System > Certificate.

- 7 Click the Root tab.

You should see the new certificate on the list.

- 8 Open up a browser and run the following command, substituting the appropriate server name, application name, UserName and Password (in red below).

```
https://<SERVERNAME>/<APPLICATION NAME>/  
start.swe?SWEEExtSource=siebelpda&SWEEExtCmd=ExecuteLogin&UserName=<USER  
LOGIN>&Password=<PASSWORD>
```

- 9 When a dialog appears, click Yes.

To complete root certificate installation on PPC 2002 device

- 1 From a web browser, navigate to the Microsoft Web site and download and launch the following executable file:

AddRootCert.exe.

- 2 Double-click to open the executable file.

A list of certificates appears.

- 3 Select certca.cer.
Information for the certca.cer Certificate appears.
- 4 Click Install Certificate.
- 5 Following successful installation, click OK.

Process of Installing the Siebel Handheld Application

Before you deploy the Siebel Handheld application, there are several tasks you need to perform.

NOTE: If you are setting up your Siebel Handheld application to allow end user translation functionality, see ["Installing and Setting Up End User Translation Functionality"](#) on page 35.

This process includes the following tasks:

- ["Editing the Handheld Application Installation Configuration File"](#) on page 86
- ["Enabling Handheld User Database Backup"](#) on page 89
- ["Deploying Patches to the Handheld Application with Direct Server Sync"](#) on page 93
- ["Deploying Handheld Application Patches with Companion Sync"](#) on page 94
- ["Creating Handheld Application Upgrade Kits for Companion Sync PDA"](#) on page 95
- ["Downloading Patches to the Handheld Device"](#) on page 96

Editing the Handheld Application Installation Configuration File

The Siebel Handheld application setup.ini file configures the Siebel Handheld Client application installer. Before you deploy a custom-configured Siebel Handheld application, you must update the parameters in the setup.ini file so that the correct values are written to the device registry before distributing the client installer to end users.

The setup.ini file resides in the Siebel Handheld application directory. To modify this file, create a Siebel Handheld installation directory on the network, or create and duplicate a custom DVD-ROM for distribution to end users. This installation directory must include the same files and directory structure as the original DVD-ROM. Then, modify the setup.ini file in the custom installation directory.

NOTE: If you wish to set up parameter values other than default values, add the parameter to the setup.ini file and add the proper values.

Table 20 lists the parameters that you may need to modify in the setup.ini file, their default value, and a description of the parameter.

Table 20. Siebel Handheld setup.ini Parameters

Parameter	Default Value	Description
Version	7.8	Version of the desktop Siebel application against which the Siebel Handheld version synchronizes.
Application Title	Siebel Sales for CE	The Siebel Handheld application. This value must match the name of the application as it is specified in Siebel Tools.
ApplicationName	Siebel Sales for CE	The Siebel Handheld application. This value must match the name of the application as it is specified in Siebel Tools.
ApplicationSplashText	Sales Handheld	The Siebel Handheld application name as shown on the splash screen.
EnableRemote	N	Used for Integrated Sync. The default value is "N". Valid values are "Y" = [Enable Remote Sync] checkbox is selected, "N" = [Enable Remote Sync] checkbox is unselected in handheld sync window.
MultiCurrency	True	Required for the application to handle multiple currencies.
SyncURL	<i>http://Web Server Name or IP address/ Virtual Directory Name</i>	Required for all synchronization methods. This value is entered in the registry on the handheld. See "Changing the SyncURL on Siebel Handheld Devices" on page 92 for more information on this parameter.
[EndUserLocalization] Section		
User DefinedLang	Y	
LogUserDefinedLangErrors	N	
[Printing] Section		See Appendix F, "Print Configuration Settings," for more information on the parameters used to configure printing.
[Backup] Section		Enables handheld database backups. See "Enabling Database Backup" on page 90 for more information on settings for the parameters in this section of the setup.ini file.

Table 20. Siebel Handheld setup.ini Parameters

Parameter	Default Value	Description
[ApplicationLocation] Section		Specifies where the Siebel Handheld application and database are installed. See "Setting Up Siebel Handheld Application Installation on a CompactFlash Card" on page 91 for more information on the parameters in this section of the setup.ini file.
InternetOptionReceiveTimeout	600000	Length of time to receive data (except data extraction) from the server before the handheld client times out. This parameter only applies to synchronizations using Direct Server Sync. In milliseconds. The default value, 600000, is 10 minutes.
InternetOptionSendTimeout	600000	Length of time to send data to the server in a single call the handheld client times out. This parameter only applies to synchronizations using Direct Server Sync. In milliseconds. The default value, 600000, is 10 minutes.
InternetOptionDataExtractionTimeout	900000	Length of time to extract data from the server to the handheld device the handheld client times out. This parameter only applies to synchronizations using Direct Server Sync.
[Logging] Section		
TXNErrorLevel	1	This level controls the extent of transaction error information received from the server. The default value is 1. Valid values are 0 = no log information, 1 = report txn errors in the client log, txnerror.hh. A "Transaction Errors Reported" message appears during sync when txn errors occur. To view errors, double click the message.

Table 20. Siebel Handheld setup.ini Parameters

Parameter	Default Value	Description
DefaultLogLevel	2	<p>The default value is 2. You can set the value to any of the following:</p> <ul style="list-style-type: none"> -1 = NO LOGGING 0 = LOG_SYSTEM 1 = LOG_ERROR 2 = LOG_WARNING 3 = LOG_INFO, INCLUDING SQL TRACING 4 = LOG_DEBUG <p>The log messages with level equal to or lower than the set value will be logged. For example, if the default log level is set to 2, the messages belonging to System, Error, and Warning log levels will be logged. If the DefaultLogLevel is -1, no logging will be provided.</p>
MaxLogFileSize	2000	<p>This is the maximum log file size in KB. If the program finds the size of the latest log file is greater than this value, a new log file should be used for logging.</p>
MaxSavedLogFiles	3	<p>Determines the number of log files to save on the device. It does not include the one currently used by the program. If the value is set to 2, then the valid log file names are siebel_log.txt, Siebel_log1.txt, and siebel_log2.txt. Siebel_log.txt is the current log file. Siebel_log1 is an older one and Siebel_log2 is the oldest.</p>
PressureThreshold	29	<p>Prompts user to restart application after 30 visits, thereby freeing application memory.</p>

Enabling Handheld User Database Backup

Siebel Handheld infrastructure provides a way to automatically back up a snapshot of the user’s database and current settings, and to restore those settings in the event of a total device failure. The backup functionality automatically copies all the necessary files to a single compressed file. Each time the user backs up, the backup process creates a new copy of the file and deletes older backups. The backup process must close the application in order to copy the RDBMS and handheld configuration files. After the files are copied, it automatically restarts the application.

The backup feature must be enabled in the application. If the backup feature is enabled, a backup is created during every synchronization. This way, the user retains an up-to-date snapshot of the database, and older backup versions are removed.

When the database backup feature is enabled, a database backup occurs automatically at the end of each synchronization. This makes the overall time to synchronize somewhat longer. The size of the database and the speed of the CompactFlash card also affect the time it takes to complete synchronization.

NOTE: Backups should not be used as a replacement for synchronization.

Setting Up Database Backups

In order to back up the database you must do the following:

- Provide users with an external memory card.
- Install the Siebel Handheld application with the backup functionality enabled. See, [“Enabling Database Backup” on page 90](#).
- Instruct users to back up their database on a regular basis.

Backing Up to External Media

It is recommended that you back up to external media—for example, a CompactFlash card or the embedded backup storage that is included in many devices.

Enabling Database Backup

Before users can back up the database on their handheld devices, you must first enable the Backup menu item on the Siebel Handheld application. This requires editing the setup.ini file to enable backup.

NOTE: Backup should be kept on external media or built-in storage. Trying to set the location to the main memory, such as \My Documents, will not work.

The following is an example of the default settings for the backup parameters:

```
[Backup]
BackupLocation = \Storage Card\Siebel Backup
BackupEnabled = N
```

- BackupEnabled = [Y/N] The default is N (No). Change this setting to Y (Yes) to enable the Backup menu item and to trigger a backup to occur automatically after each synchronization.

If the product is installed with Backup = N, the backup menu item is disabled. You need to change the parameter, then reinstall the product in order to enable the menu item.

- BackupLocation = [Backup location] The default is an external storage card. Specify the location where you want the data backed up.

For more information on the setup.ini file, see [Chapter 8, “Installing the Handheld Application.”](#)

Restoring from a Backup

For information on restoring a database from a backup, see [“Backing Up and Restoring Data with the Siebel Handheld Client”](#) on page 115.

Installing Print Templates in the Siebel Handheld Install Directory

If your application allows printing, you must include all print templates in the template subdirectory of the Siebel Handheld Install directory. The print templates are language-specific, so copy the templates to the template subdirectory within the language directory of the language you are deploying (for example, ...\\ENU\\Template). If the template includes double byte characters, such as Japanese string, you must save the template files as Unicode (UTF16) files. For supported language codes, see *System Requirements and Supported Platforms* on Siebel SupportWeb.

See [Appendix F, “Print Configuration Settings”](#) for more information about Printing.

Setting Up Siebel Handheld Application Installation on a CompactFlash Card

The default, when installing Siebel Handheld applications, is to install both the application and the database into RAM on the device. In most instances, there is sufficient available memory, and end users are satisfied with the application performance. There are situations, however, where you may need to optimize storage on the device.

If you need to maximize main memory availability, you can install the application binary files on an external location such as a CompactFlash card. Installing the data on the CompactFlash card is not recommended because performance likely degrades.

You can specify, in the application’s setup.ini file, where the application files and database files are to be installed. By default, this is set to the handheld device. In the ApplicationLocation section of the setup.ini file, there are two parameters. The following shows the default settings for these parameters:

```
[ApplicationLocation]
ApplicationBinariesLocation = Device
ApplicationDataLocation     = Device
```

- ApplicationBinariesLocation = Device. The default is Device. The other value is CF (CompactFlash).
- ApplicationDataLocation = Device. The default is Device. It is recommended that you always install the data files on the device.

After you have edited the setup.ini file, follow the instructions for installing the Siebel Handheld application on the client.

Changing the SyncURL on Siebel Handheld Devices

For Direct Server Sync (DSS), SyncURL is used to locate the Web Server and the virtual directory so that the handheld synchronization client can communicate with the handheld synchronization server. For example:

SyncURL = http://web server name or IP address/virtual directory name

You can reset the SyncURL by re-installing the application with the updated setup.ini file.

For Companion Sync set up, the SyncURL parameter identifies the configuration file that will be accessed on the handheld client for synchronization.

For example, the default configuration file for Sales Handheld is named salesce.cfg. For companion sync set up, the SyncURL value should be http://xxxx/salesce where xxxx could be any text string.

Installing the Siebel Handheld Application from External Media

Users who synchronize in DSS mode may not have a PC, and so may not be able to create a partnership and synchronize using Microsoft ActiveSync. You can install the application for each user through a standard partnership, or you can configure a stand-alone installer.

During the installation, the InstallShield Wizard screen prompts you by asking,

would you like to deploy a CAB file to enable rapid installation for additional devices?

You can configure a stand-alone installer by selecting Yes.

You are prompted to select a language for the application and to specify a location for the CAB file. The installer creates the CAB file in the location you specify.

The CAB file is a self-extracting file that includes all the files needed to install the Siebel Handheld application on the handheld device. When you single-click the file, the CAB file installs the application.

You may create an image of the Handheld Installer that can be loaded onto external media such as a CompactFlash card. When you create a stand-alone installer platform, a Cabinet file (CAB) is created in a location that you specify. The CAB file name should be siebel.pocketpc_arm.CAB. You can copy the CAB file to a CompactFlash card, insert the card into the handheld device, and single-click on the file to install the Siebel Handheld application on the device.

NOTE: When installing the application on the device, the end user is asked if he or she wants to install the application in the default directory. Regardless of the user's answer, the application is always installed in the directory specified by the setup.ini file. Therefore, the only way to change the directory the application is installed in is to modify the parameters in the ApplicationLocation section of the setup.ini file.

Distributing Siebel Handheld Application Patches

The Siebel Handheld patch delivery mechanism, PatchAgent, is a tool that automates the deployment of patches to handheld devices as part of the synchronization process. It allows administrators to distribute patches to end users with minimal involvement by the users.

During synchronization the PatchAgent executable is called, and if it detects a handheld patch, it automatically installs the patch on the handheld device. In order for PatchAgent to detect and deploy the patch, the patch files must be created and placed in the directory where PatchAgent expects to find the files.

Deploying Patches to the Handheld Application with Direct Server Sync

In order to set up patch deployment for Direct Server Sync users, you need to patch the Siebel server and patch one handheld client which serves as the “model” from which patch files are pulled. Then the patch files are then packaged and placed in the location on the server where PatchAgent expects to find the files. The next time the end user synchronizes with Siebel server, the patch is installed onto his or her device.

For more information on how the patch process works with synchronization, see [“Downloading Patches to the Handheld Device”](#) on page 96.

To set up patch deployment

- 1 On Siebel server, verify that the following directories exist. If they do not, create the directories.
 - C:\patch\AppBinDir
 - C:\patch\WinDir

NOTE: You may specify a drive other than C:. However, the directory names must be specified as shown above.
- 2 Apply the patch to Siebel server.
- 3 Apply the patch to one handheld client.
- 4 Examine the handheld directory (My Device\Program Files\Siebel Handheld) and copy the files with the latest date to the Siebel Server directory (C:\patch\AppBinDir).
- 5 Examine the handheld directory (My Device\Windows) and copy the files with the latest timestamp to the Siebel Server directory (C:\patch\WinDir).
- 6 From the DOS prompt, change directory to *Siebel Root*\SWEApp\BIN.
- 7 Execute the following command to stage the patch files and the patchlist.txt in the correct location on the server:

```
C:\Siebel Root\SWEApp\BIN>createpatchlist /s c:\patch /t c:\Siebel  
Root\sweapp\cepatch
```

/s – source directory. The directory where the patch files were moved.

/t – target directory. The directory where PatchAgent checks for the patch files.

NOTE: You may specify a drive other than C:. However, the location of the source and target directories must be specified exactly as shown.

After the patch files have been moved and the patch list created, the following message appears: "Patch List has been successfully created in *Siebel Root\SWEApp\cepatch* files transferred successfully."

The patch files are now ready to be deployed to Direct Server Sync end users.

Deploying Handheld Application Patches with Companion Sync

In order to set up patch deployment for Companion Sync users, you need to create a "model" of a patched Siebel Mobile Web Client and a patched handheld client. Then you pull the designated patch files and place them in the correct directory on the end user's Mobile Web Client. You may use Siebel Anywhere to create upgrade kits to automate this process of distributing patch files to your end user's Mobile Web Client. The next time the end user uses Companion Sync to synchronize their handheld device with the Siebel Mobile Web Client, the patch is installed on the device.

For more information on how the patch process works with synchronization, see ["Downloading Patches to the Handheld Device" on page 96](#).

To set up patch deployment

- 1 On Siebel server, verify that the following directories exist. If they do not, create the directories.
 - C:\patch\AppBinDir
 - C:\patch\WinDir
- 2 Apply the patch to Siebel server.
- 3 Apply the patch to Siebel Mobile Web Client.

This Mobile Web Client serves as the model from which the patch files can be pulled.
- 4 Apply the patch to one handheld client.

This handheld client serves as the model from which the patch files can be pulled.
- 5 Examine the handheld directory (My Device\Program Files\Siebel Handheld) and copy the files with the latest date to the Siebel Server directory (C:\patch\AppBinDir).
- 6 Examine the handheld directory (My Device\Windows) and copy the files with the latest timestamp to the Siebel Server directory (C:\patch\WinDir).
- 7 From the DOS prompt, change directory to C:\Siebel Root\SWEApp\BIN.

- 8 Execute the following command to move the patch files to the correct location and generate a patchlist.txt file:

```
C:\Siebel Root\SWEApp\BIN>createpatchlist /s c:\patch /t c:\Siebel
Root\sweapp\cepatch_xxx (where xxx is the language [enu, esn, and so on])
```

/s – source directory. The directory where the patch files were moved.

/t – target directory. The directory where PatchAgent checks for the patch files.

NOTE: You may specify a drive other than C:. However, the location of the source and target directories must be specified exactly as shown.

After the patch files have been moved and the patch list created, the following message appears: "Patch List has been successfully created in *Siebel Root\SWEApp\cepatch_xxx* files transferred successfully."

- 9 Create the following directory on the end user's Mobile Web Client: *Siebel Root\client\cepatch_xxx* (where xxx is the language [enu, esn, and so on]), and push the files from the *\Siebel Root\SWEApp\cepatch_xxx* directory on Siebel server to the *Siebel Root\client\cepatch_xxx* on the Mobile Web Client.

NOTE: Siebel Anywhere upgrade kits can be used to carry out this step.

Creating Handheld Application Upgrade Kits for Companion Sync PDA

NOTE: This step is optional. Additionally, you must have a license for Siebel Anywhere to distribute patches to end users.

You may use Siebel Anywhere upgrade kits to remotely distribute self-extracting zip files to your end users' PCs. You can use self-extracting zip files to create new directories and immediately extract files into the directories. Create one upgrade kit for each of the following:

- Create the Siebel Mobile Web Client upgrade kit (Siebel Client Revisions).

Navigate to the Siebel image location for the current software version such as D:/Siebel_Install_Image/7.8.1.0, and then navigate to the patch directory. Configure the zip file to self-extract in the *Siebel Root\client\BIN* directory on the end user's Mobile Web Client.

- Create the Siebel Handheld upgrade kit (Siebel Client Revisions).

Create a self-extracting zip file that includes the files in the *Siebel Root\SWEApp\cepatch* directory on the server. Configure the zip file to self-extract in the *\client\cepatch* directory on the end user's Mobile Web Client.

- Create any other upgrade kits as needed (for example, the Siebel Customer Repository File).

See *Siebel Anywhere Administration Guide* for detailed information on creating upgrade kits.

NOTE: If there are read-only files on the Mobile Web Client, the end user may need to change the file attributes to read-write before receiving and installing the upgrade kits. Contact Siebel Technical Support for the list of files whose attributes need to be changed. You may use Siebel Anywhere to distribute a batch script that makes this change.

Downloading Patches to the Handheld Device

Patches are downloaded as part of the synchronization process. Once the patch is staged, the patch is downloaded the next time the end user synchronizes the handheld with Siebel server. The end user synchronizes as he normally would using Direct Server Sync or Companion Sync. First, any transactions are uploaded from the handheld device. Then:

- If a patch needs to be applied to the handheld, the synchronization process terminates, and the patch process is started, which downloads the patch.
- If no patch needs to be applied, the synchronization process continues until the process is complete.

After a successful patch installation, Siebel Handheld Sync will launch automatically and continue the extraction.

If the patch files are not successfully downloaded, the end user is prompted to restart the patch process. The end user must locate and launch patchagent.exe manually. Then, once the patch is successfully installed, the end user is prompted to complete the synchronization.

7

Synchronization Conflict Handling and Recovery with Handheld

This chapter includes the following topics:

- [“Preventing Synchronization Transaction Conflicts with Siebel Handheld” on page 97](#)
- [“Recovering Error Data in Siebel Handheld” on page 102](#)

Preventing Synchronization Transaction Conflicts with Siebel Handheld

When multiple end users synchronize with a remote database, transaction conflicts may occur which can result in data loss. The Extended Pick and Insert Failure functionality minimizes synchronization conflicts. If transaction conflicts are unavoidable, then Siebel Handheld Sync Service captures the transaction information so that the data can be recovered. The combination of these features eliminates the potential for data loss.

There are two features that minimize synchronization transaction conflicts.

- Extended Pick processing
- Insert Failure processing

The next several sections describe these features in detail.

Extended Pick Processing in Siebel Handheld

The handheld is used to capture and record transactions entered by the handheld user. During synchronization, these transactions are processed on the server. A situation may arise in which a transaction fails when it is applied to the Siebel server (through Direct Server Sync) or Siebel Mobile Web Client (through Companion Sync)—both of which are referred to as server. For example, a Siebel Handheld user creates a professional call activity for one of his contacts. However, since he last synchronized with the server, the contact involved in this transaction was deleted from the server database. When he tries to synchronize his handheld, the server does not find his contact, and the call activity for the contact cannot be inserted into the server database. To generalize this example, any transaction that involves data selected through picklists or pick applets fails on the server if that pick data is not present at the time of synchronization.

With many handheld users synchronizing with Siebel server and modifying data at different times, this scenario is not uncommon.

The following describes how a pick transaction is recorded on the handheld device and processed on the server during synchronization. Assume that the handheld user wants to create a new call activity for the contact. In order to do this, the user inserts a new record in the Professional Call screen and “picks” the desired contact. When the contact is selected on the handheld, the Row Id of the contact (Contact Id) is recorded. However, on the handheld, the application does not record any of the pick map fields associated with the contact; only the Contact Id is recorded. When the user synchronizes his handheld, that Contact Id is used to locate the contact record in the server database. The Contact Id is then used to retrieve all of the fields used in the pick map for the Contact Id (Last Name, First Name, Middle Initial, Address, City, State, Zip Code, and so on).

In order to minimize pick processing failures, the handheld must record the pick row Id and all of the pick map data that is required for a successful transaction. This data must be recorded at the time of the pick, so that it can be passed to the server for processing. This enhanced functionality is called Extended Pick processing. Now, when the user synchronizes, the transaction is processed on the server as follows:

- The synchronization process first looks for the pick record on the server database. For example, to add an activity it looks for the contact and, if it finds the contact, it retrieves the necessary data and adds the activity. This is the default behavior.
- If the server does not find the pick map record in the database and extended pick processing is enabled, it retrieves the pick record Id and pick map data from the handheld transaction and applies the data directly to the server.

Enabling Extended Pick Processing in Siebel Handheld

You can enable Extended Pick processing globally or at the business component level when configuring the Siebel Handheld application. When the *DefaultHandheldSyncPickMode* parameter is enabled every handheld pick transaction is subject to pick processing.

To enable extended pick processing globally

- 1 From the application-level menu, choose Navigate > Site Map > Administration-Mobile > Application Administration.

- 2 Click the Settings view tab, then Query on the following value:

DefaultHandheldSyncPickMode

If there is no such record, a new record with that value should be created. See [Table 21](#) for the values to enter.

Table 21. Application Settings

Setting Name	Value	Description
DefaultHandheldSyncPickMode	NoFail	Turns Extended Pick processing ON.
	FailOnError	Turns Extended Pick processing OFF This is the default behavior if the parameter is not specified in the Settings view.

To enable extended pick processing at the business component level

- When enabling extended pick processing at the business component level, the user property is defined on specific business components. The syntax for setting Extended Pick on a business component and the parameter values ([Table 22](#)) follow:

HandheldSyncPickMode=Fieldname|Mode

Table 22. Business Component User Property Parameters

Business Component User Property	Parameter	Value	Description
HandheldSyncPickMode	<i>Fieldname</i>	—	Specify the field name as defined in Siebel Tools.
	<i>Mode</i>	NoFail	Turns Extended Pick processing ON.
		FailOnError	Turns Extended Pick processing OFF.

You may apply Extended Pick processing to multiple fields in a single business component, using the following syntax:

HandheldSyncPickMode=Fieldname1|Mode1, Fieldname2|Mode2

The setting on the business component takes precedence over the setting defined in the Settings view. For example, you can use the business component setting to nullify the global application of Extended Pick. Conversely, you can enable Extended Pick processing on specific business components if the setting in the Settings view has disabled the functionality.

For more information, see *Using Siebel Tools*.

[Table 23](#) shows the combined effect of the settings in the Application-Mobile > Settings View and on a business component.

- The DefaultHandheldSyncPickMode setting is omitted from application settings.

- If there is no setting on a particular business component, the setting defined in the Settings view applies.
- If there is no setting defined in the Settings view, or on the business component, the default behavior is for Extended Pick to be turned OFF.

In [Table 23](#), read down the Tools configuration column and across to the Mobile Administration View Setting to see the combined result. For example, a NoFail configuration in Tools combined with a FailOnError setting in the Mobile Administration View results in the combined effect NoFail.

Table 23. Combined Effect of Extended Pick Settings for Business Components

Tools Configuration (User Property) HandheldSyncPickMode=	Mobile Administration View Settings DefaultHandheldSyncPickMode=		
	NoFail	FailOnError	Omitted
NoFail	NoFail	NoFail	NoFail
FailOnError	FailOnError	FailOnError	FailOnError
Omitted	NoFail	FailOnError	FailOnError

Insert Failure Processing in Siebel Handheld

When the server executes an insert transaction and the insert fails, there are two ways the insert failure can be handled:

- A record is logged that indicates the insert failed, and synchronization continues. This is the default insert behavior. The Conflict Administration screen can be used to recover the data.
- The insert failure is logged, including details of the failure, and synchronization is interrupted. This is the FailOnError behavior. FailOnError behavior guarantees that, should an insert fail, data loss does not occur since synchronization is stopped until the circumstances causing the failure are resolved.

NOTE: If FailOnError processing takes place, synchronization is interrupted. The synchronization process continues to fail until the problem is resolved. End users must contact their system administrators to recover from the failure. The recovery effort may involve modifying transactions queued for processing, modifying data on the server, or reentering transactions through the Siebel Handheld application.

Handling Insert Failures

You can enable Extended Pick processing globally or at the business component level when configuring the Siebel Handheld application. The following setting applies globally throughout the application. When FailOnError is specified, every failed insert interrupts synchronization.

DefaultHandheldInsertMode.

You can specify the value for this setting through the Settings view in the Administration-Mobile screen.

Table 24 shows the settings for this parameter.

Table 24. Insert Failure Processing Parameter Setting

Parameter	Mode Value	Description
DefaultHandheldInsertMode	NoFail	Insert failures are logged and synchronization continues. This is the default behavior.
	FailOnError	Insert failures are logged and synchronization terminates. The system administrator must intercede to recover from this failure.

Optionally, you can enable Extended Pick processing at the business component level.

HandheldInsertFailMode=*Mode*

The user property is defined on specific business components. The setting in the business component takes precedence over the setting defined in the Settings view. Table 25 shows the syntax for setting the Insert Fail Mode on a business component and the parameter values. These settings are made in Siebel Tools.

Table 25. Business Component User Property Parameter

Business Component User Property	Parameter	Value	Description
HandheldInsertFailMode	<i>Mode</i>	NoFail	Insert failures are logged and synchronization continues. This is the default behavior.
		FailOnError	Insert failures are logged and synchronization terminates. The system administrator must intercede to recover from this failure.

Table 26 shows the combined effect of the setting in the Settings view and the setting on a business component.

- The business component setting always takes precedence over the settings defined in the Administration-Mobile > Settings view.
- If there is no setting on a particular business component, the Applications Settings value applies.
- If there is no setting in either the Settings view or on the business component, the default behavior is the same as NoFail. Insert failures are logged and synchronization continues.

In [Table 26](#), read down the Tools Configuration column and across to the application settings value to see the combined result. For example, a NoFail BC setting combined with a FailOnError application setting results in the combined effect NoFail.

Table 26. Combined Effect of Insert Failure Settings

Tools Configuration (User Property) HandheldInsertFailMode=	Application Settings Value DefaultHandheldInsertMode=		
	NoFail	FailOnError	Omitted
NoFail	NoFail	NoFail	NoFail
FailOnError	FailOnError	FailOnError	FailOnError
No Setting on Business Component	NoFail	FailOnError	NoFail

Recovering Error Data in Siebel Handheld

Selected synchronization and conflict errors are captured to the database, and can be accessed through the Conflict Administration screens. This mechanism is always enabled. For more information on recovering error data, see [“Obtaining Error Details from Siebel Handheld Synchronization Sessions”](#) on page 68.

8

Installing the Handheld Application

This chapter includes the following topics:

- [“Preparing to Upgrade from a Previous Siebel Handheld Release” on page 103](#)
- [“Installing the Siebel Handheld Application” on page 103](#)
- [“Reinstalling the Siebel Handheld Application” on page 106](#)
- [“Uninstalling the Siebel Handheld Application” on page 106](#)

Preparing to Upgrade from a Previous Siebel Handheld Release

The Siebel Handheld application cannot be upgraded directly on the device. To upgrade your existing application and to migrate your data and settings to Siebel 7.8 use the following process:

- Back up the handheld device by synchronizing to your database. See, [“Synchronizing Data on the Siebel Handheld Device” on page 117](#).
- Uninstall your Siebel Handheld application. See, [“Uninstalling the Siebel Handheld Application” on page 106](#).
- Then install the new version of your Siebel Handheld application. See [“Installing the Siebel Handheld Application” on page 103](#).

Installing the Siebel Handheld Application

There are two ways to install software onto any Windows-powered handheld device. The first is to create a partnership between a desktop or laptop PC and the handheld device using Microsoft ActiveSync. The second is to install the application from type of external media.

NOTE: It is important to remember that end users must synchronize their handheld devices to download the application configuration and populate the database before they can use the application. Therefore, an administrator may install the application for an end user, but the synchronization must occur using the end user’s name and password.

Installing Handheld for Companion Sync Users

The following procedure lists the Handheld installation steps for Companion Sync users:

To install the Siebel Handheld application using Companion Sync

- 1 Using Microsoft ActiveSync, establish a partnership between the handheld device and the PC.
- 2 On the PC network or DVD-ROM, locate the folder where the Siebel Handheld Application folder is installed, then double-click setup.exe.

The installation process begins.

- 3 From the Choose Setup Language window, choose the language you want to use for the installation and click OK.
- 4 At the Synchronization Options screen, choose the Companion Sync option and then click Next.
The next screen displays and asks, "Would you like to deploy a CAB file to enable rapid installation for additional devices?"

NOTE: If you want to create a stand-alone installer, choose Yes, and then click Next.

- 5 To install the application on the device, click Next.
- 6 Select the desired language of the Siebel Handheld Application, and click Next.

A window appears showing the setup status, followed by several DOS windows.

- 7 The Add/Remove Programs dialog appears. This is followed by the Installing Applications dialog that asks if you want to install in the default directory. Click Yes to install the Siebel Handheld application on the handheld device.

NOTE: The default directory in the Applications dialog is the directory specified by the system administrator in a setup file. So that the application works correctly, the Siebel Installer installs the application in the default directory. Therefore, even if you specify a different location for the application, the application is installed in the default location.

During the installation, the Installing Applications dialog box displays a progress bar. It may take several minutes to install on the handheld device. When the application has been downloaded to the handheld device, the Application Downloading Complete dialog box displays on the PC.

- 8 Click OK.

A window appears informing you that setup has finished installing the Siebel Handheld application on your computer.

- 9 Click Finish.

After installing the Siebel Handheld application and Siebel Handheld Sync, you must perform an initial synchronization before the application can be used. Refer to ["Synchronizing Data on the Siebel Handheld Device" on page 117](#) for the procedure for synchronizing your data.

See [Chapter 5, "Data Filtering,"](#) for more information on using Direct Server Sync and setting filters.

Installing Handheld for Direct Server Sync Users

Most DSS users do not have access to a PC for creating a partnership with their handheld device. In this case, the administrator has to create a temporary partnership with each user's device and install the application. Siebel Handheld applications can be installed in DSS mode using the Siebel Installer as described in this section.

To install the Siebel Handheld application using DSS

- 1 Using Microsoft ActiveSync, establish a partnership between the handheld device and the PC.
- 2 On the PC network or DVD-ROM, locate the folder where the Siebel Handheld Application folder is installed, then double-click setup.exe.

The installation process begins.

- 3 From the Choose Setup Language window, choose the language you want to use for the installation and click OK.
- 4 At the Synchronization Options screen, choose the Direct Server Sync option and then click Next.

The next screen displays and asks, "Would you like to deploy a CAB file to enable rapid installation for additional devices?"

NOTE: If you want to create a stand-alone installer, choose Yes, and then click Next.

- 5 To install the application on the device, click Next.
- 6 Select the desired language of the Siebel Handheld Application, and click Next.

A window appears showing the setup status, followed by several DOS windows.

- 7 The Add/Remove Programs dialog appears. This is followed by the Installing Applications dialog that asks if you want to install in the default directory. Click Yes to install the Siebel Handheld application on the handheld device.

NOTE: The default directory in the Applications dialog is the directory specified by the system administrator in a setup file. So that the application works correctly, the Siebel Installer installs the application in the default directory. Therefore, even if you specify a different location for the application, the application is installed in the default location.

The Siebel Handheld installation automatically installs SSCE Service Pack 1 and overwrites existing files on your system. A message may appear asking if you want to replace existing files. Respond by tapping "Yes to All."

During the installation, the Installing Applications dialog box displays a progress bar. It may take several minutes to install on the handheld device. When the application has been downloaded to the handheld device, the Application Downloading Complete dialog box displays on the PC.

- 8 Click OK.

A window appears informing you that setup has finished installing the Siebel Handheld application on your computer.

- 9 Click Finish.

After installing the Siebel Handheld application and Siebel Handheld Sync, you must perform an initial synchronization before the application can be used. Refer to [“Synchronizing Data on the Siebel Handheld Device” on page 117](#) for the procedure for synchronizing your data.

See [Chapter 5, “Data Filtering,”](#) for more information on using Direct Server Sync and setting filters.

Reinstalling the Siebel Handheld Application

Follow the steps below to reinstall your Siebel Handheld application.

To reinstall the Siebel Handheld application

- 1 Before you reinstall the current application, you must first uninstall the current application on your device. See [“Uninstalling the Siebel Handheld Application” on page 106](#) for more information.
- 2 Once you have uninstalled the application, you may then reinstall the application or install the newer version. See [“Installing the Siebel Handheld Application” on page 103](#), and follow the instructions for installing the Siebel Handheld application.
- 3 Synchronize your Siebel Handheld application. See [“Synchronizing Data on the Siebel Handheld Device” on page 117](#) and follow the instructions for synchronizing your data.

NOTE: If you are using Companion Sync to synchronize your data, synchronize the Siebel Handheld database with the Siebel Remote database.

Uninstalling the Siebel Handheld Application

Uninstalling the application deletes the database files as well as the application files.

CAUTION: Before you uninstall your application, you must synchronize your database to save any changes to your data since the last synchronization. If you do not synchronize before uninstalling, these changes will be lost. See [“Synchronizing Data on the Siebel Handheld Device” on page 117](#) and follow the instructions for synchronizing your data.

To uninstall the Siebel Handheld application

- 1 Select Start > Settings.
- 2 Select the System tab and tap Remove Programs.
- 3 From Remove Programs, select the Siebel Handheld application and tap Remove.

NOTE: A dialog box appears saying that a file cannot be deleted. This occurs because a file may still reside in memory. Ignore this message and tap OK to delete all application and database files. No additional steps are required to remove the application and database files.

9

Working with Siebel Handheld Applications

This chapter includes the following topics:

- ["Components of the Siebel Handheld Interface" on page 107](#)
- ["Navigating the Siebel Handheld Interface" on page 110](#)
- ["Navigating a List of Records in the Siebel Handheld Application" on page 111](#)
- ["Entering Data with the Siebel Handheld Application" on page 112](#)
- ["Finding and Querying Data in the Siebel Handheld Application" on page 112](#)
- ["Printing with the Siebel Handheld Application" on page 114](#)
- ["Exporting Data with the Siebel Handheld Application" on page 114](#)
- ["Setting User Preferences in the Siebel Handheld Application" on page 115](#)
- ["Backing Up and Restoring Data with the Siebel Handheld Client" on page 115](#)
- ["Synchronizing Data on the Siebel Handheld Device" on page 117](#)
- ["Synchronization Troubleshooting with the Siebel Handheld Client" on page 120](#)
- ["Improving Siebel Handheld Application Performance" on page 121](#)

Components of the Siebel Handheld Interface

The components of the handheld interface include the Screens menu, Show drop-down list, application-level menu, Queries drop-down list, toolbar, and status bar.

Figure 2 shows the components of the Siebel Handheld application.




Figure 2. Siebel Handheld Screen Components

Screens Menu

The screens menu is the first level of navigation in the Siebel Handheld application. When you launch the Siebel Handheld application for the first time, this tab is labeled Screens unless you have configured a start up view to appear. When you tap the screens menu, a drop-down list of all available screens appears. Tap the desired screen in the list to navigate to it.

For information about configuring a start up view, see ["Setting User Preferences in the Siebel Handheld Application"](#) on page 115.

Show Drop-Down List

The Show drop-down list is the second level of navigation in the Siebel Handheld application. This is where you choose views for the selected screen.

Application-Level Menu

The application-level menu consists of the File, Edit, View, and Help menus. Tap a menu to select a menu option. The options that are available in each menu vary depending on the task you are performing.

Queries Drop-Down List

Up to two predefined queries, or business object filters are displayed in the Queries drop-down list. The list displays the query chosen when you synchronized (or the default filter if you did not change the Set Filters selection) and the All Records query, if it is defined. For more information, see [Chapter 5, "Data Filtering."](#)

Siebel Toolbar

The Siebel toolbar has buttons for frequently used functionality like record navigation and querying. You can configure your toolbar and specify which buttons are displayed. See ["Configuring User Interface Elements in Siebel Handheld" on page 25.](#)

- Tap the New Record button to add a new record to the active list or form.
- Tap the Back button to navigate to the previous view.
- Tap the Forward button to navigate to the view you were in before you selected the Back button.
- Tap the Record Navigation buttons to move through records in a form or a list.
- Tap the New Query button to begin a new query in a form or a list.
- Tap the Execute Query button to run the query you just created.
- Tap the Maximize Minimize Applet button to expand the active applet so that it is the only applet displayed and takes up the entire screen display. This allows you to see more columns or more rows of data at one time. Tap again and the screen displays two applets.

Customizing the Toolbar

You can customize which buttons appear on your toolbar by selecting View > Customize Toolbar from the application menu.

To add and remove buttons from the toolbar, drag and drop the desired buttons between the Choose Toolbar Buttons dialog box and the toolbar.

Minimize Button

The Minimize button appears in the upper-right corner of your window. When you tap the Minimize button, the application minimizes, but does not close. To reopen the minimized application, from the Start menu, tap the Siebel Handheld icon. To close (exit) the application, choose File > Exit.

Do not confuse the Minimize button that appears in the upper right corner with the Maximize Minimize Applet button that appears on the Toolbar.

Status Bar

The status bar appears at the bottom of the application window. It provides information about the current view.

Navigating the Siebel Handheld Interface

Navigating the Siebel Handheld application is achieved through the screens menu, the Show drop-down list, drilling down, drilling across, toolbar buttons, and toggling.

Screens Menu

The screens menu provides the first level of navigation. Here you select the screen you want to work in. For more information about the screens menu, see [“Components of the Siebel Handheld Interface” on page 107](#).

Show Drop-Down List

The Show drop-down list is the second level of navigation. After you have selected a screen from the screens menu, select a view from the Show drop-down list. Views in the Show drop-down list are specific to each screen.

For example, in the Activities screen you can pick the My Activities view from the Show drop-down list.

Toggling Between Applets

A maximum of two applets can be displayed at one time in a Siebel Handheld application. In situations where there are more than two applets configured and a Toggle button has been configured, you may tap the Toggle button on the applet. Or you may select View > Toggle from the menu to toggle between applets.

Expandable Fields

Due to the limited screen size on the handheld, it is not always easy to view the data in a field without scrolling or resizing the field width. Therefore, some fields that could contain large amounts of text are expandable—that is, the data can be viewed in a text box. An ellipsis (...) appears in the field to indicate that the field is expandable. When you tap the ellipsis, a text box opens showing the data in that field. When you step off the field, the text box closes.

In form applets, an ellipsis is always visible in those fields that are expandable. However, in list applets, due to space constraints, the ellipsis is not always visible in expandable fields. When you tap on an expandable field in a list applet, the ellipsis appears. Once the ellipsis appears, you tap the ellipsis to open the text box.

URLs in Applet Fields

Tapping on a field that contains a URL value launches the URL in PocketIE.

Navigating a List of Records in the Siebel Handheld Application

Within the view you select from the Show drop-down list, you can view detailed information on a record. When records are displayed in a list, you can drill down or drill across the record to get additional details.

Drilling down occurs when you tap a hyperlink in a record and are taken to another view within the current screen. For example, if you are in the Accounts screen, and tap the Account Name hyperlink, you navigate to the details for that account. You do not leave the Accounts screen; you just move deeper into it.

NOTE: Hyperlinks are indicated by blue underlined text as long as they are set up this way in User Preferences. For more information see ["Setting User Preferences in the Siebel Handheld Application"](#) on page 115.

Drilling across a record occurs when you tap a hyperlink in a record and are taken to another view in a different screen. For example, tapping a hyperlink in the Accounts column of a contact record in the Contacts screen takes you to the record for that account in the Accounts screen.

Dynamic drilldown occurs when you tap a hyperlink in a record and are taken to another screen or just another view. Where you navigate to depends on the content in the drilldown field.

History Arrows

To navigate back to views you have recently displayed, tap the Back button. After you have used the Back button, you can use the Forward button to navigate back to your original screen and view.

NOTE: The History arrows only allow you to navigate between views. These arrows do not allow you to recover data that may have been entered or deleted in another view.

Record Navigation Buttons

Use the Record Navigation buttons to move back and forth through a set of records. The navigation buttons are described in [Table 27](#).

Table 27. Record Navigation Buttons

Button	Description
	Navigates back to the previous record in the list or form.
	Navigates forward to the next record in the list or form.
	Navigates back a view based on the navigation history. You can define which views are part of the history. If a view is set to not be recorded as part of the history, the back button won't go back to that view.

Entering Data with the Siebel Handheld Application

There are several different methods for entering data in the Siebel Handheld application. Tap the up arrow next to the Input Panel button to select a method. See the user guide for your device for information on using the different input methods.

Working with Columns in the Handheld Client

Data is displayed in lists and forms in your Siebel Handheld application. You can organize and work within it in a number of ways to better suit your needs.

There are several ways in which to organize columns in a list. You can:

- Sort data by up to three columns
- Resize columns
- Change the order in which the columns appear
- Show and hide columns
- Lock columns for horizontal scrolling

You can sort records in a list by tapping in the column header of the column in which you want to sort the records. If the green column sort indicator points up, the column is sorted in ascending order. If it points down, the column is sorted in descending order.

If you need to sort by more than one column, you can open the Sort Order dialog box to sort up to three columns at one time. Open the Sort Order dialog box by choosing View > Advanced Sort from the application-level menu.

Resize columns by tapping and dragging the divider between the column headings until the column is the desired size.

You can change the order of columns using the Columns Displayed dialog box. Open the Columns Displayed dialog box by choosing View > Columns Displayed.

Show and hide columns using the Columns Displayed dialog box. In the Available columns list, select the items you want to show and tap the arrow to move the selected items to the Selected columns list. To hide columns, select the items and tap the arrow to move the selected items to the Available columns list.

Lock or unlock columns by tapping and holding the column header.

Finding and Querying Data in the Siebel Handheld Application

You can search for data using the Find or Query functionality in your Siebel Handheld application.

About Find in Handheld

Use Find to do a simple search for a record. You can access Find by choosing Edit > Find View > Find from the application-level menu. This launches the Find dialog box, in which you can enter your search criteria. The asterisk wildcard function (*) can be used in the search criteria. [Figure 3](#) shows an example of the Find dialog window with the following fields: Look In, Last Name, Type, Last Call Date, Primary Specialty, and Rep Specialty.

NOTE: There may be a slight variation in your version of Siebel software, and the Find dialog box may not look exactly as shown here.



Figure 3. Find Dialog Box

About Queries in Handheld

Use Query to locate a number of records containing a specific set of criteria. There are a number of ways in which to perform query tasks in your Siebel Handheld application.

Creating a Query

To begin a query, you can choose Edit > Query > New from the application-level menu, or you can tap the New Query button on the toolbar. Both provide you with a blank form or list where you can enter your query criteria, depending on where you are in the application when you invoke the command. The asterisk wild card function (*) can be used in the search criteria.

Executing a Query

After you have created the query, you can execute it by choosing Edit > Query > Run from the application-level menu or by tapping the Execute Query button in the toolbar.

Refining a Query

You can refine your current query by choosing Edit > Query > Refine from the application-level menu.

Printing with the Siebel Handheld Application

You may print from any view in the Siebel Handheld application that has been configured to support printing. When you print from the handheld, a document that has been configured for the view is printed. You can print directly to a printer, or, if you are not connected to a printer at the time, you can queue your print jobs and wait until you have access to a printer to print your documents.

NOTE: When you print from a view, you are not necessarily printing what is visible on the screen at the time. Every field on the screen may not be relevant for the document. The document may contain only a portion of what is in the view, and it may also contain data that is not viewable at the time. A separate applet, which often cannot be viewed in the user interface, is configured specifically for printing.

The print templates used to generate the printed are installed during the time of setup.

For a list of supported printers, see *System Requirements and Supported Platforms* on Siebel SupportWeb.

Print from the Siebel Handheld application by choosing File > Print. If you are connected to a printer, the print job runs. If you are not connected to a printer, the print job is sent to a print queue. View the print queue by choosing File > Print Queue.

Exporting Data with the Siebel Handheld Application

You may export data from any view in your application in HTML format or as tab delimited text and save it to a file. This file can be viewed in applications such as Microsoft Pocket Word, Microsoft Pocket Excel, and Internet Explorer.

To export data, select File > Export to open the Export dialog box.

In the Export dialog box, you may specify the following:

- **Format.** Specify either HTML or Tab delimited text file.
- **Export.** Select Only active applet to export only the data in the active applet. Select All applets in view to export the data in all visible applets.
- **Output file name.** By default, the file is saved in the temp directory with the filename "output." You may tap Browse to specify a different location or filename.
- **Paste Output to Clipboard.** Select the checkbox to save the data to the clipboard.

- **Open file.** Select the checkbox to automatically open the file. When you tap OK in the Export dialog box, the data is exported to the specified file, and the file is automatically opened.

NOTE: You must specify a valid output format for the application. See [Table 28](#) for the correct formats to specify for the supported applications.

Table 28. Export Data Options

To export data to	Do the following
Microsoft Word	Set Format to "Tab delimited text file."
Microsoft Excel	Select the "And paste output to clipboard" check box. The Output format may be set either to HTML or "Tab delimited text file." Paste the data from the clipboard into an Excel spreadsheet.
Microsoft Internet Explorer	Set Format to HTML.

Setting User Preferences in the Siebel Handheld Application

You can customize aspects of your Siebel Handheld application from the User Preferences dialog box. Access the User Preferences dialog box by choosing View > User Preferences from the application-level menu.

In the User Preferences dialog box you can:

- Set a default startup screen.
- Set number of maximum history threads to be saved.
- Set the maximum percentage of the display area that the parent applet can take up.
- Change font size.
- Customize list spacing, column width settings, and grid lines.
- Customize your calendar's default view, start time, time slot interval, and default appointment duration.

Backing Up and Restoring Data with the Siebel Handheld Client

It is recommended that you back up your data to an external device—for example, a CompactFlash card or a Secure ID card. If the handheld device is damaged, the backup may not be retrievable. If you store your backups in RAM, depending on the size of your application and data extract, you may decrease the amount of memory available for the application, and your application performance may suffer.

Automatic Backup After Synchronization

The automatic backup feature must be enabled in the application by your System Administrator. If the backup feature is enabled, a backup is automatically created at the end of every synchronization. This way, you have an up-to-date snapshot of the database.

CAUTION: You must never synchronize your data to the handheld device and then restore the database using an older copy of the database. If you do, the next time you synchronize, the application tries to rewrite changed transactions. This can cause data integrity problems. Therefore, when the database backup feature is enabled, a database backup occurs automatically at the end of each synchronization.

Keep in mind that enabling automatic backup makes the overall time to synchronize somewhat longer. The size of the database and the speed of the CompactFlash card also affect the time it takes to complete synchronization.

For more information, see ["Enabling Handheld User Database Backup" on page 89](#).

Backing Up Data

The following procedure describes how to back up the database on the handheld device.

To back up the database

- 1 From the application-level menu, choose File > Backup.

NOTE: If the Backup menu item is disabled, contact your system administrator to have backup enabled in your application.

A dialog box appears, telling you that backing up the data will restart the application and prompts you to confirm that you want to continue.

- 2 Tap Yes to start the backup.

A status dialog box appears indicating that the backup is in progress and may take a few minutes. The Handheld configuration files and data is copied to the backup location specified in the setup.ini file. Typically, the backup location is a CF or SD card.

A dialog box appears telling you whether the backup succeeded and asks if you want to return to the application.

- 3 Tap Yes to return to the application.

NOTE: If the backup fails, consult your system administrator.

Restoring Data from a Backup

In order to restore the application to its previous state, the user should contact the system administrator. Any work performed on the handheld device since the last backup will be lost.

To restore the database

- 1** Remove the external flash card from the damaged device and place it in a new handheld device where the application has been installed.
- 2** Navigate to the \Program Files\Siebel Handheld folder.
- 3** Start the restore by tapping the BackupUtility file twice.
A dialog box appears, asking you to confirm that you want to restore the device from a previous backup.
- 4** Tap Yes.
A status dialog box appears, indicating that the restore is in progress. The backup utility restores the files to the state when the backup was performed. A dialog box appears telling you if the restore was successful. If successful, it asks you to confirm that you want to restart the Siebel Handheld application.
- 5** Tap Yes to start using the application.

Synchronizing Data on the Siebel Handheld Device

You must synchronize the data on your handheld device:

- After you install or upgrade the Siebel Handheld application.
- Before uninstalling the Siebel Handheld application.
- On a regular basis to keep your data synchronized with Siebel Server and Siebel Mobile Web Client.

The sections that follow describe how to synchronize using Companion Sync (CS), Direct Server Sync (DSS) and Direct Server Sync via Proxy (DSSvP), and provide some troubleshooting tips.

Using Siebel Handheld Synchronization with the Handheld Client

Siebel Handheld Synchronization differs depending on whether users synchronize through Companion Sync or Direct Server Sync. The following topics show you how to launch and use Handheld Synchronization for each method.

NOTE: A given user can only synchronize using one method. For example, it is not possible to install a Siebel Handheld application that a particular user will synchronize both to the Siebel Mobile Web client database through Companion Sync and also to the Siebel Server database directly through Direct Server Sync.

Using Companion Synchronization with the Handheld Client

If you are using Companion Sync, you must follow a three-step process to synchronize handheld, remote, and server databases. Immediately before and after every Siebel Remote sync, you must perform a Companion Sync. This process can be time consuming for the end user and difficult for the administrator to enforce.

Integrated Sync eliminates the need for you to initiate three separate sync sessions for each Siebel Remote sync.

Before using Integrated Sync, if you are using a CFG file other than siebel.cfg to invoke Siebel Remote Sync, you must specify or add the parameter RemoteCfgName in the [pda] section of salesce.cfg (for Sales Handheld)

siasalesce.cfg (for SIA Sales Handheld)

For example, RemoteCfgName=<anyname>.cfg. If you do not specify this parameter, it will default to siebel.cfg. This parameter is used by Siebel Handheld Sync to invoke Siebel Remote. It applies only when synchronizing using the Integrated Sync option.

Integrated Sync automatically initiates each of the following synchronization steps:

- 1** Handheld Upload and Processing - Handheld transactions are uploaded to the companion PC and processed.
- 2** Siebel Remote Synchronization - The Siebel Mobile Client is synchronized with the Siebel server. Transactions on the mobile client database are uploaded to the Siebel server, and changes to the Siebel server are downloaded to the mobile client database.

CAUTION: If there is a handheld patch staged on the server, synchronization terminates and the patch is installed. After the patch installation is completed, you are prompted to synchronize again (using either Integrated Sync or Companion Sync) to complete the data extraction and download (that is, move to Step 3). It is critical that you synchronize a second time after the patch installation is completed. If you fail to do so, you will not be able to start the Siebel Handheld application.

- 3** Handheld Data Extract and Download - Data is extracted from the mobile client database to the handheld device database.

You may use Companion Sync to synchronize your handheld with Siebel Mobile Client as many times as you wish between Integrated Sync sessions. However, it is recommended that you conduct Integrated Sync sessions frequently so that the Siebel Remote synchronization process does not take long periods of time to complete and update conflicts are minimized.

To perform Companion Sync from the PC

- 1** From the companion PC, establish a Microsoft ActiveSync connection to the handheld device.
- 2** From the companion PC, choose Start > Programs > Siebel Handheld Sync.

The Siebel Handheld Sync dialog box appears.

- a** Enter your name and password.

- b** Select the Perform Remote Sync check box to perform an Integrated Sync.

If you want to do Companion Sync only, then unselect the Perform Remote Sync check box.

Selected Bypass Set Filters skips the step of selecting the filters and immediately starts the synchronization process. If you select Bypass Set Filters, then the filters that you selected the last time you synchronized are used. If this is the first time you are synchronize, then the default filters are used.

- 3** Tap Start.

NOTE: Tap Default Filters to restore the filter selection to the default setting.

- 4** Tap OK and tap Start to begin synchronization.

- a** The Siebel Handheld Sync dialog box appears. If "Perform Remote Sync" was selected, this is followed by the Siebel Remote dialog box. When synchronization has successfully completed, the Finished dialog box appears.
- b** If a handheld patch needs to be installed, the synchronization process is interrupted and the patch is installed. After the patch is installed, you must restart Siebel Handheld Sync to complete the data extract process. If you fail to do so, you cannot start your application.
- c** The Finished dialog box appears indicated that the synchronization has successfully completed.

- 5** Tap OK to exit Siebel Handheld Sync.

NOTE: If synchronization errors occur, an error dialog box appears.

Companion Sync can also be performed in the method described for Direct Server Sync via Proxy in "Using Direct Server Synchronization with the Handheld Client" on page 119.

To perform Companion Sync from the handheld device

- 1** From the application-level menu, choose File->Synchronization.
- 2** In the Sync window select the "Enable Remote Sync" checkbox. It is disabled by default.
For information on changing the parameter value for EnableRemote in the setup.ini file, see "Siebel Handheld setup.ini Parameters" on page 87.
- 3** See the steps for synchronizing using DSSvP in the procedure "To synchronize with the Siebel application server" on page 120.

Using Direct Server Synchronization with the Handheld Client

There are two methods for synchronizing between the handheld device and the Siebel application server:

- Direct Server Sync (DSS) provides synchronization between the Siebel Handheld application and the Siebel application server.

- Direct Server Sync via Proxy (DSSvP) provides synchronization between the Siebel Handheld application and the Siebel application server, using the desktop or companion PC to provide the network connection between the handheld device and the server.

To synchronize with the Siebel application server

- 1** If you are synchronizing using DSS, create a direct network connection through a modem or a direct LAN connection.

If you are synchronizing using DSSvP, establish an ActiveSync connection between the handheld device and the PC.
- 2** From the application tap File > Synchronize.

The Siebel Handheld Sync dialog box appears.
- 3** Enter your user name and password.
- 4** Tap Start.

The Siebel Handheld Sync dialog box appears.
- 5** Tap OK to exit Siebel Handheld Sync, and the application will launch automatically.

NOTE: If synchronization errors occur, an error dialog box appears.

Synchronization Troubleshooting with the Siebel Handheld Client

This section lists potential error messages that are associated with synchronization. In addition, this section helps to understand transaction errors.

General Synchronization Errors

There are a number of different errors that can occur when synchronization does not complete successfully, for example:

- Faulty wire connection
- Server crash
- Insufficient memory
- Login error

When these errors occur, the user should exit Siebel Handheld Sync and launch the application again.

NOTE: When you restart Siebel Handheld Sync, you may see an error message that says that another instance of syncmanager.exe is running. You are asked whether you want to terminate the first instance or not, and you should choose Yes.

Transaction Conflicts

Transaction conflicts are minimized when customers adhere to the standard configuration practices outlined in this document. However, even when proper configuration practices are followed, conflicts can occur for a variety of reasons. For example, if a field value is updated on both the handheld client and the server between synchronization events, a transaction update conflict occurs. In this instance, the user is presented with an error dialog after synchronization has completed.

A transaction consists of one or more smaller transactions called mini-transactions. For example, if you update several fields in a record, the update to the record counts as a single transaction, and each update to a field is a mini-transaction. Individual fields are skipped when update conflicts occur. Changes to any field that has been updated on the server since the last sync (perhaps by another Handheld user) are discarded (but logged and returned as errors to the user). All non-conflicting fields normally are updated. Except for field-level conflicts, which are skipped when they occur, a transaction is applied in its entirety, and at this point will either succeed or fail in its entirety.

Improving Siebel Handheld Application Performance

If you find that the performance of the Siebel Handheld application is very slow or begins to degrade, the following can help to improve the application performance:

- Verify that you are using a Siebel supported device for your application. See *System Requirements and Supported Platforms* on Siebel SupportWeb.
- When you run the Siebel Handheld application, it is recommended that you do not run any other applications. By doing so, you maximize the amount of memory that is available to run the application.
- Increase the amount of memory that is allocated for running applications.
- Installing the binaries to a CompactFlash card. For more information, see ["Setting Up Siebel Handheld Application Installation on a CompactFlash Card" on page 91.](#)

To increase application memory

- 1 From the Start menu, select Settings.
- 2 Select the System tab and tap Memory.
- 3 Move the slider bar so that more memory is allocated to Program Memory, then tap OK.

10 Using Siebel Sales Handheld

This chapter includes the following topics:

- ["About Using Siebel Sales Handheld" on page 123](#)
- ["About Managing Contacts in Siebel Sales Handheld" on page 123](#)
- ["Managing Accounts in Siebel Sales Handheld" on page 125](#)
- ["Developing Opportunities in Siebel Sales Handheld" on page 128](#)
- ["Managing Customer Relationships in Siebel Sales Handheld" on page 132](#)
- ["Developing Quotes in Siebel Sales Handheld" on page 136](#)
- ["Managing Orders in Siebel Sales Handheld" on page 140](#)
- ["Tracking Expenses in Sales Handheld" on page 142](#)

About Using Siebel Sales Handheld

Siebel Sales Handheld provides mobile sales professionals with the sales tools and information to manage sales processes such as opportunity, account and contact management while they are in the field or away from their desk.

Although the sales process varies by organization, certain similarities do exist. Siebel Sales Handheld has been designed so that each organization can adapt its usage to best suit mobile business needs while building on similarities in practices found across many sales organizations. Organizations can use Siebel Sales Handheld in conjunction with the Siebel Sales Web client application or as a stand-alone product.

Sales representatives may use the handheld to record contact and account information, manage opportunities, schedule sales activities, check product and pricing information, provide quotes and orders, and create expense reports. In addition, sales administrators and sales managers can customize the software to fit current business needs.

About Managing Contacts in Siebel Sales Handheld

Contacts are individuals with whom your company conducts business or expects to conduct business in the future. Contacts can be employees of other companies, independent consultants, vendors, or personal acquaintances. Contacts may be associated with several accounts, but a contact may be primary on only one account. Contacts may be associated with a number of opportunities, including those that are not related to their accounts.

The following contact management topics are included in this section:

- [“Scenario for Managing Contacts in Sales Handheld” on page 124](#)
- [“Adding Contacts in Sales Handheld” on page 124](#)
- [“Associating Contacts with Opportunities in Sales Handheld” on page 125](#)

Scenario for Managing Contacts in Sales Handheld

At a trade show, a sales representative exchanges business cards with the people she meets. Instead of waiting until she returns to her office, the sales representative uses Siebel Sales Handheld to enter essential contact information. When she returns to her office, she identifies individuals that may be possible sources for leads.

As the sales representative works with each contact, the possibility of doing business—an opportunity—may arise. If so, she can then create an opportunity and associate contacts and activities with it to track important milestones and key players for closing the deal.

Adding Contacts in Sales Handheld

Use the My Contacts or Personal Contacts views to enter information about your contacts. Contacts entered using the Personal Contacts view are not shared with team members.

To add a contact

- 1 Navigate to the Contacts screen.
- 2 From the Show drop-down list, select My Contacts, or Personal Contacts.
 - My Contacts: Use this list for contacts that you might or might not share with the rest of your organization.
 - Personal Contacts: Use this list for contacts that are not shared with the rest of your organization.
- 3 Tap the New Record button, then fill the Last Name and First Name fields.
- 4 From the Show drop-down list, choose More Info, and then complete additional fields, as needed.

The following table describes some fields in the Contact form.

Fields	Comments
Job Title	A text field that displays the Contact’s professional title.
Account	Displays the primary account with which the contact is associated. A contact may be associated with more than one account, but may be the primary contact on only one account at a time. To associate the Contact with an Account, navigate to the Contacts > Accounts view (if configured).

Fields	Comments
Work Phone Number	A text field that displays the contact's work telephone number.
Site	A default value that populates automatically based on the location of the primary account.

Associating Contacts with Opportunities in Sales Handheld

A contact may be a source of revenue for your company. Potential revenue-generating events are called Opportunities. You will want to associate a contact with an existing opportunity to track information about both the opportunity and the contact. For more information, see ["About Creating Opportunities in Sales Handheld" on page 129](#).

To associate a contact with an existing opportunity

- 1 Navigate to the Contacts screen.
The My Contacts list appears.
- 2 In the My Contacts list, select the contact with whom the opportunity will be associated.
- 3 From the Show drop-down list, choose Opportunities.
- 4 Tap in the Opportunities list, and then from the File Menu, select New Record.
The Add Opportunities list appears.
- 5 In the Add Opportunities list, select the opportunity to associate with the contact, and then tap OK.

Managing Accounts in Siebel Sales Handheld

An account represents the relationship between your company and the companies or individuals with whom you do business. You use the Accounts screen and its associated views as the primary navigation tool for your customer interactions.

The following topics related to account and account management are included in this section:

- ["Scenario for Managing Accounts in Sales Handheld" on page 126](#)
- ["Creating Accounts in Sales Handheld" on page 126](#)
- ["Associating Activities with Accounts in Sales Handheld" on page 127](#)
- ["Associating Opportunities with Accounts in Sales Handheld" on page 128](#)

Scenario for Managing Accounts in Sales Handheld

A prospect is interested in learning more about the products and services that your company sells. The sales representative sets up a time for a sales call later in the week.

During the sales call, the sales representative asks a number of questions to determine the account structure of the prospect's business to help the representative determine how best to fit the prospect's product needs. The sales representative learns that the prospect's business has a total of four locations, and that sales and service are billed through the main office, although each location receives a billing statement.

After the sales representative meets with the prospect, he creates the account structure for his business.

Creating Accounts in Sales Handheld

When you identify a possible lead, the lead can be added as an account. You can then begin to add and track information about the account.

To create an account

- 1 Navigate to the Accounts screen.
The My Accounts list appears.
- 2 Tap the New Record button.
- 3 In the Name field tap the ellipsis (...), enter a name for the account, and then select More Info.
- 4 In the More Info view, complete the necessary fields.

To add account addresses

- 1 Navigate to the Accounts screen.
The My Accounts list appears.
- 2 Select the account record, and from the Show drop-down list, choose Addresses.
- 3 In the Account Addresses view, tap to select the Addresses list, and then from the File menu, select New Record.
- 4 Select an existing account, or tap New to add a new address.
- 5 Complete the fields for the address, and tap the Primary field to display a check mark if this is the primary address for the account.

To add additional account information

- 1 Navigate to the Accounts screen.
The My Accounts list appears.

- 2 From the Show drop-down list, select More Info.
- 3 Complete the fields to add additional information.

The following table describes some fields in the More Info form. The name and address fields are automatically populated with information entered at the My Accounts and Addresses views.

Fields	Comments
Parent Account	Select the parent account from the Pick Account picklist.
Account Type	Pick the Account Type from the list. Examples are Fulfillment Shipper, Commercial, Competitor.
Account Team	Displays the primary Account Team member with which the account is associated. To associate the account with one or more team members, navigate to the Account > Account Team view.
URL	Text entry.
Industries	Displays the primary industry with which the account is associated.
Price List	Choose applicable price list from the Pick Price List dialog box.
Current Volume	Enter amount, or tap the ellipses and enter Currency Code, Exchange Date and Amount in the dialog box. Then tap OK.
Potential Volume	Enter amount, or tap the ellipses and enter Currency Code, Exchange Date and Amount in the dialog box. Then tap OK.
Status	A list of values established by your company. Status examples might be Qualified, Silver, Active.
Currency	Select the currency code from the Pick Currency Code list.

The My Accounts list appears.

Associating Activities with Accounts in Sales Handheld

An activity is a task or event that is generally, but not always, performed for a contact, account, or opportunity. You will likely have many meetings, calls, presentations, and other activities surrounding an account.

Activities provide a place to enter and track this information. If the activity entered has a time associated with it, it will appear on the Activities and Calendar screens.

To associate activities with accounts

- 1 Navigate to the Accounts screen.
The My Accounts list appears.
- 2 In the My Accounts list, select the account with which the activity will be associated.

- 3 From the Show drop-down list, select Activities.
- 4 In the Account Activities view, tap to select the Activities list, and then from the File menu, select New Record.
- 5 In the new row, complete the necessary fields.
The Type field defaults to Appointment.
- 6 Drill down on the default activity Type hyperlink to display the Activities screen's More Info view.
- 7 In the More Info form, add and edit details about the activity.
For more information, see ["Creating Activities in Sales Handheld" on page 133](#).

Associating Opportunities with Accounts in Sales Handheld

Accounts are a source of business for your company. An opportunity is a potential revenue-generating event and is another type of information that you can use to manage your accounts within Siebel Sales Handheld.

To add an opportunity to an account

- 1 Navigate to the Accounts screen.
The My Accounts list appears.
- 2 From the Show drop-down list, select My Accounts.
- 3 In the My Accounts list, select the account to which the opportunity will be associated.
- 4 From the Show drop-down list, choose Opportunities.
The Account Opportunities view appears.
- 5 In the Account Opportunities view, tap to select the Opportunities list, then from the File menu, select New Record.
- 6 In the Opportunities list, complete the necessary fields for the new record.
The Account field is automatically populated with the name of the selected account. Sales stage selections are based on the sales methods used by your organization.

Developing Opportunities in Siebel Sales Handheld

An opportunity is defined as a potential revenue-generating event. An opportunity is usually associated with an account and one or more contacts, products, activities, and quotes.

Examples of opportunities are:

- At a trade show, a company representative expresses interest in purchasing a product.
- When called by a telesales representative, a contact indicates interest in contracting maintenance services.
- In a conversation with an existing client, the client expresses an interest in upgrading to the newest product model.

The following topics related to opportunities are included in this section:

- ["Scenario for Developing Opportunities in Sales Handheld" on page 129](#)
- ["About Creating Opportunities in Sales Handheld" on page 129](#)
- ["About Sales Methods in Sales Handheld" on page 130](#)
- ["Associating a Contact with an Opportunity in Sales Handheld" on page 131](#)
- ["Associating a Product with an Opportunity in Sales Handheld" on page 131](#)
- ["About Opportunity Quotes in Sales Handheld" on page 132](#)

Scenario for Developing Opportunities in Sales Handheld

A sales representative is involved in revenue-generating and customer contact activities at her company. At a trade show she meets a prospective customer who could be a lead for a new business opportunity. Using her Siebel Sales Handheld application, the sales representative discovers that the company is listed in Siebel Sales as an account, but the person she met is not listed as a contact associated with the account.

After adding this person as a contact, the sales representative creates the opportunity. Next, the sales representative schedules meetings, records the associated activities, and associates other important contacts to the opportunity.

As the sales process continues, the sales representative gathers and updates information about the account, its contacts, and the opportunity. As the relationship grows, the sales representative can add, view, and share information and key knowledge with other members of the sales team.

About Creating Opportunities in Sales Handheld

Each time you identify an opportunity, you should create a new record.

To create an opportunity

- 1 Navigate to the Opportunities screen.
The My Opportunities list appears.
- 2 From the File menu, select New Record, and enter a name in the Name field.

- 3 From the Show drop-down list, choose More Info and complete additional fields.

The following table describes some fields in the Opportunities - More Info form.

Field	Comments
Name	A required value that identifies the opportunity.
Account	Allows you to associate an opportunity with an account.
Description	A text area for additional information about the opportunity.
Site	A default value that populates automatically when you associate the opportunity to a specific account and location.
Primary	Displays the primary Sales Team member for the opportunity. To associate the opportunity with one or more team members, navigate to the Opportunity > Sales Team view (if configured).
Rev:	Revenue. Allows you to enter the currency amount of the opportunity. This field defaults to zero.
Probability %	Allows you to enter the percentage of confidence you have that the deal will close with the specified revenue on the specified close date. Probability automatically updates based on the Sales Method and Sales Stage selected.
Expected Value	Displays a currency value that is calculated based on the potential revenue field multiplied by the value in the probability field. A lower percent in the probability field reduces the expected value that will be included in your revenue forecast.
Close Date	A required field that allows you to enter the expected date on which the opportunity will close. The default date is the same as the Created Date. It is important to modify the date, if the opportunity will close on a different date, since this date is used in revenue forecasting.
Lead Quality	A list of values established by your company that allows you to rank the quality of the lead. Default values include 1-Excellent, 2-Very High, 3-High, 4-Fair, 5-Poor.
Sales Method	A list of values established by your company that list the sales methodologies. For more information, see "About Sales Methods in Sales Handheld" on page 130 .
Sales Stage	A list of values established by your company that lists the sales stages associated with the sales method you selected.

About Sales Methods in Sales Handheld

A sales method is a formalized approach or methodology used during the sales process. A sales method can encompass all activities associated with the sales process, from prospecting to forecasting to closing deals. This approach allows sales representatives to use the most appropriate method for opportunities.

The application administrator will create and implement the sales stages your company uses, and then establish values in your Siebel application that represent these methods and stages. A recommended business practice is to designate a default sales method in your Siebel application. This practice allows a sales method to be associated with each opportunity and aids in charting and reporting accuracy.

Sales methods can differ within a company. For instance, a sales method for managing a complex multimillion dollar opportunity may include 15 stages, while a sales method for a simple low-dollar opportunity may require only four stages.

For more information about creating or implementing sales stages, see *Applications Administration Guide*.

Associating a Contact with an Opportunity in Sales Handheld

As you work with an opportunity, you will want to maintain information about the contacts associated with the opportunity. For more information about contacts, see [“Adding Contacts in Sales Handheld” on page 124](#).

The Opportunities screen’s Contacts view allows you to associate and review contact-related information for an opportunity.

To associate a contact with an opportunity

- 1 Navigate to the Opportunities screen
The My Opportunities list appears.
- 2 In the My Opportunities list, select the opportunity with which you will associate a contact.
- 3 From the Show drop-down list, choose Contacts.
- 4 Tap to select the Contacts list, and then from the File menu select New Record.
- 5 In the Add Contacts dialog box, select the contact or contacts you wish to add, and then tap OK.

NOTE: To select multiple records, tap the control key and select the contact records.

Associating a Product with an Opportunity in Sales Handheld

Specific products can be associated with an opportunity. For example, if a customer is interested in purchasing a new product model, this information can be entered in the Products view.

After the information is entered, you can drill down on the product to find additional information such as product features and prices.

To associate a product with an opportunity

- 1 Navigate to the Opportunities screen.
The My Opportunities list appears.
- 2 In the My Opportunities list, select the opportunity with which a product will be associated.
- 3 From the Show drop-down list, choose Products.
- 4 In the Opportunity Products view, tap to select the Products list, and then from the File menu, select New Record.
- 5 In the new row, tap the arrow in the Products field.
- 6 In the Pick Product dialog box, select the product, and then tap OK.
- 7 Complete the remaining fields, as needed.

About Opportunity Quotes in Sales Handheld

The Opportunity Quotes view displays quotes that have been generated for a specific opportunity. After adding products to an opportunity in the Opportunity Products view, you can navigate to the Opportunity Quotes view to initiate Auto Quote functionality or to manually create a quote. For more information, see ["Creating Quotes in Sales Handheld" on page 136](#).

Managing Customer Relationships in Siebel Sales Handheld

An organization's records should accurately reflect the amount of work required and performed to maintain customer satisfaction. This practice avoids duplication of effort if a different or an additional team member has to get involved. It also keeps everyone up to date as to exactly what activities have occurred and when they have occurred.

The following topics related to Activities are included in this section:

- ["About Activities in Sales Handheld" on page 133](#)
- ["Scenario for Managing Activities in Sales Handheld" on page 133](#)
- ["Creating Activities in Sales Handheld" on page 133](#)
- ["Delegating Activities in Sales Handheld" on page 133](#)
- ["Associating Contacts with Activities in Sales Handheld" on page 134](#)
- ["Adding General Activities Using the Calendar in Sales Handheld" on page 134](#)

About Activities in Sales Handheld

Activities are various tasks or events that are performed for contacts, accounts, and opportunities. Activities that are given start times are automatically entered on the activities screen and your calendar.

Scenario for Managing Activities in Sales Handheld

While working away from his desk, a sales manager receives a call from a customer who wants to visit the sales manager's company for an executive summary meeting. The customer also wants the sales team to perform a product demonstration. The sales manager schedules the meeting using his handheld. After his next synchronization, the meeting appears on calendars of his team members. The sales manager delegates the tasks required to prepare for the meeting, such as preparing presentation slides, reserving a conference room, and configuring the demo system. These activities appear in the sales manager's Activities screen and calendar for the customer's account.

As the sales manager and his team members complete the activities, the activities are marked as done, providing key status information about the opportunity.

Creating Activities in Sales Handheld

Throughout the day, you have new tasks to accomplish and activities to monitor. These activities are part of your business. By keeping track of these activity records on your handheld, you make sure your team members know about these tasks, and you create a valuable history of your past interactions with customers.

To create a new activity

- 1 Navigate to the Activities screen.
The My Activities list appears.
- 2 From the File menu, select New Record, and in the new row, complete the necessary fields.
A default value is provided in the activity Type field.
- 3 Drill down on the hyperlink value in the Type field.
- 4 In the More Info form, pick the appropriate activity type from the list, and complete the fields.

Delegating Activities in Sales Handheld

If you work as part of a sales team or are the manager, an important part of managing your activities includes managing other people's activities. When an activity needs to be performed by someone else, you can reassign or delegate it to an employee.

To delegate an activity

- 1 Navigate to the Activities screen.
The My Activities list appears.
- 2 In the My Activities list, find the activity that needs to be delegated.
- 3 From the Show drop-down list, select Employees.
- 4 In the Activity Employees view, tap to select the Employees list, and then from the File menu, select New Record.
- 5 In the Add Employees list, select the employees to whom the activity will be assigned.
- 6 To make an employee the primary for the activity, tap the Primary field to display a check mark.

Associating Contacts with Activities in Sales Handheld

When you add an activity to your calendar, you may also want to have a record of contacts who will be participating in the activity.

To associate contacts with activities

- 1 Navigate to the Activities screen.
The My Activities list appears.
- 2 In the My Activities list, select the activity with which a contact will be associated.
- 3 From the Show drop-down list, select Contacts.
- 4 In the Activity Contacts view, tap to select the Contacts list, and then from the File menu, select New Record.
- 5 In the Add Contacts dialog box, select the contacts, and then tap OK.

Adding General Activities Using the Calendar in Sales Handheld

General activities and appointments must have the Planned Start and Duration fields populated in order to be displayed in the correct time slot on the Daily Calendar view.

To add a general activity in the Calendar view

- 1 Navigate to the Calendar screen.
- 2 From the Show drop-down list, select Daily, Weekly, or Monthly.
- 3 For My Weekly or My Monthly, select the day on which you want to schedule a general activity.

- 4 From the File menu, select New Record.

You can also tap an open time slot within the daily view.

- 5 In the new record, complete the necessary fields for the appointment or task.

Some fields are described in the following table.

Field	Comments
Type	The type of activity. Activity types might be call, email-outbound, demonstration, and so on.
Planned Start	This date-time field defaults to the time selected when you created the new appointment.
Duration	When the duration is updated, the planned completion time is automatically adjusted.
Account	Complete this field if the activity is related to a particular account.
Repeat	Tap the check box to display a check mark if the appointment or task is recurring. Siebel Handheld Calendar does not support modification of single instances of recurring activities. For example, if you delete or modify an appointment scheduled to recur daily for 10 days, the entire series will be deleted.
Repeat Until	The end date of a repeating appointment.

To specify contact participants

- 1 Navigate to the Calendar screen and locate the day the task or appointment occurs.
- 2 Drill down on the task or appointment hyperlink to display the Calendar form.
- 3 From the Show drop-down list, select Contact Participants.
- 4 In the Calendar Contacts view, tap the Contacts list to select it, and then tap the New Record button.
- 5 In the Add Contacts dialog box, select contacts and tap OK.

To specify employee participants

- 1 Navigate to the Calendar screen and locate the day the task or appointment occurs.
- 2 Drill down on the task or appointment hyperlink to display the Calendar form.

If the appointment or task repeats over time, you will be asked to indicate if changes to the appointment should be applied to the specific occurrence, or to all occurrences. From the Show drop-down list, select Employee Participants.
- 3 From the Show drop-down list, select Employee Participants.
- 4 In the Calendar Employees view, tap the Employees list to select it, and then tap the New Record button.

- 5 In the Add Employees dialog box, select employees, and then tap OK.

Developing Quotes in Siebel Sales Handheld

When the customer is ready to purchase a product or service, you can develop a quote using Siebel Sales Handheld that includes specific prices for products and services with related payment terms.

The following topics related to quote development in Sales Handheld are included in this section:

- ["Scenario for Developing Quotes in Sales Handheld" on page 136](#)
- ["Creating Quotes in Sales Handheld" on page 136](#)
- ["Using Auto Quote in Sales Handheld" on page 137](#)
- ["Adding Quote Items in Sales Handheld" on page 138](#)
- ["Printing Quotes in Sales Handheld" on page 140](#)

Scenario for Developing Quotes in Sales Handheld

A mobile sales representative relies on quotes to create formal offers to clients for a variety of products and services that her company provides. Using Siebel Sales Handheld she can produce accurate offers at the customer site, with up-to-date product and pricing information. When details and pricing are finalized, the sales representative can print the quote and deliver it promptly to the customer.

Creating Quotes in Sales Handheld

Quotes includes effective dates, price lists, and discounts used in pricing products and services. Before any of this information can be added to a quote, however, the quote must be created with basic information.

To create a quote

- 1 Navigate to the Opportunities screen.
The My Opportunities list appears.
- 2 In the My Opportunities list, select the opportunity for which the quote will be generated.
- 3 From the Show drop-down list, select Quotes.
- 4 In the Opportunity Quotes view, tap the Quotes list to select it, and then tap the New Record button.

The new quote is automatically assigned a record identifier, a revision number, the default status of In Progress, and a created date.

- 5 In the Name field, enter a name for the quote.
When you tab to an adjacent field, the quote name becomes a hyperlink.
- 6 Drill down on the hyperlink in the Name field to display the More Info form where you can add quote details.

Using Auto Quote in Sales Handheld

If you are working with an opportunity for which the products and solutions have already been specified in the Opportunity Products view, there is a faster method to generate a quote. You can use the Auto Quote button.

When Auto Quote generates a quote from an opportunity, quote line items are created for each product under the opportunity that has the Auto Quote flag checked. The Quote Item fields are populated from the corresponding Opportunity Product's fields, as shown in [Table 29](#).

Table 29. Quote Item Fields Populated by Opportunity Product Fields

Opportunity Product Fields	Quote Item Fields
Product	Product
Product Quantity	Extended Quantity Requested
Write-In Product (not exposed in application)	Write-In Product (not exposed in application)
Expected Delivery Date	Requested Delivery Date (not exposed in application)
ID (not exposed in application)	Opportunity Product ID (not exposed in application)

In addition, information from the generated quote's Quote # field is copied to the Opportunity Products' Quote # field. The Part Number field of the generated Quote Item is determined by the quote item's product.

[Table 30](#) shows the quote record fields that are automatically completed when Auto Quote is used to create a quote.

Table 30. Quote Fields Completed with Auto Quote

Field	Value
Quote #	System generated
Revision	1
Name	Quote number, unless the user provides another value
Opportunity	The opportunity from which the quote is automatically generated

Table 30. Quote Fields Completed with Auto Quote

Field	Value
Account	The account for the opportunity
Account Site	The location of the account associated with the opportunity
Status	In Progress
Active	Checked
Currency	The currency code for the opportunity
Price List	The price list associated with the opportunity's account
Sales Rep	User ID
Effective	Current date
Through	Current date plus 30 days (30 days is determined by the QUOTE_EXPIRATION_PERIOD LOV)

To create a quote using Auto Quote

- 1 Navigate to the Opportunities screen.
The My Opportunities list appears.
- 2 In the My Opportunities list, select the opportunity for which the quote will be generated.
- 3 From the Show drop-down list, select Quotes.
- 4 In the Opportunity Quotes view, tap Auto Quote.
A new row appears in the Quotes list, with the Quote #, Revision, Status and Created date filled in.
- 5 Provide a quote name, edit other fields as necessary, and then drill down on the hyperlink in the quote Name field.
- 6 In the Quote detail form, enter additional information about the quote.
 - a Select the applicable predefined Discount that will be applied to the quote.
 - b Select the applicable predefined Price List.

NOTE: Auto Quote functionality is only available in the Opportunities screen Quotes view.

Adding Quote Items in Sales Handheld

Using the Quotes screen, you can add line items to quotes that you are developing. If the Auto Quote method is used, products associated with opportunities appear automatically as line items with any applicable discounts.

Line items can be used to:

- Add new products as line items

- Apply manual price adjustments to the line items using the Toggle button.

NOTE: Siebel Handheld does not support complex quotes (bundled line items). Only simple line items can be created.

To add line items

- 1 Navigate to the Opportunities screen.
The My Opportunities list appears.
- 2 In the My Opportunities list, select the opportunity with which the quote is associated.
- 3 In the Show drop-down list, select Quotes.
- 4 In the Opportunity Quotes view, locate the quote in the list and drill down on the Name hyperlink.
The quote detail form appears.
- 5 From the Show drop-down list, select Quote Items.
- 6 In the Quote Line Items view, tap the Line Items list, and then tap the New Record button.
- 7 In the Line Items list, complete the required fields.

If you are entering more than one line item, repeat Step 6 and Step 7 until each line item has been entered. Tap the Toggle button to display a form that you can use to add Item discounts and other adjustments.

NOTE: Beginning with Siebel Handheld version 7.8, pricing changes are not applied until after you have synchronized with the server (for Direct Server Sync) or Mobile Web Client (for Companion Sync). Any changes to the Product, Part #, Price List, Discount %, and Qty fields will clear the price fields.

After synchronizing, the Totals field is updated with the Quantity Requested total, and the Order record Item Total and Total fields are updated based on the sum of the Line Item Start Price and Net Price fields, respectively.

To delete line items

- 1 Navigate to the Quotes screen.
The My Quotes list appears.
- 2 In the My Quotes list, select the quote containing the line item that will be deleted, and choose Quote Items from the Show drop-down list.
- 3 In the Quotes Line Items view, select the quote item in the list.
- 4 From the Edit Menu, select Delete Record.

NOTE: Quote revisions are not supported on the handheld.

Printing Quotes in Sales Handheld

Once the customer has expressed significant interest, it is often appropriate to present a hard copy quote.

To print a quote

- 1 Navigate to the Quotes screen.
The My Quotes list appears.
- 2 In the My Quotes list, select the quote containing the line items that will be printed.
- 3 From the Show drop-down list, select Quote Items.
- 4 Align the infrared ports on the handheld device and the printer.
- 5 In the parent Quotes form, tap the Print button.

Managing Orders in Siebel Sales Handheld

After you have completed the initial quote, and the customer has agreed to the products and prices you have presented, you create a sales order.

The following order management topics are included in this section:

- ["Creating Orders in Sales Handheld" on page 140](#)
- ["Adding Order Line Items in Sales Handheld" on page 141](#)
- ["Entering Terms and Totals in Sales Handheld" on page 142](#)

Creating Orders in Sales Handheld

You can create orders from quotes manually or by using the Auto Order button.

To create an Auto Order from your quote

- 1 Navigate to the Quotes screen.
The My Quotes list appears.
- 2 In the My Quotes list, select the quote from which an order will be generated.
- 3 From the Show drop-down list, select Orders.
- 4 In the Quotes list, select the quote, and then in the Orders list tap AutoOrder.
A new record appears in the Orders list, with the order date, number, type, status and so on, filled in.

- 5 In the Orders list, drill down on the Order # hyperlink.
- 6 Tap the Orders Line Items list to select it, and then tap the New Record button.
A new row appears in the Line Items list.
- 7 Tap in the Products field.
The Pick Products dialog box appears.
- 8 Select the product to add as a line item, and tap OK.

To manually create an order

- 1 Navigate to the Orders screen.
- 2 The My Sales Orders list appears.
- 3 Tap the New Record button.
A new row appears in the Sales Orders list.
- 4 Complete the necessary fields for the new order record.
From the Show drop-down list, choose More Info to display a form where you can add more details.

Adding Order Line Items in Sales Handheld

Once the initial sales order is created, you can complete the line items that make up the order.

- 1 Navigate to the Orders screen.
The My Sales Orders list appears.
- 2 In the My Sales Orders list, select the order to which line items will be added.
- 3 From the Show drop-down list, select Line Items.
- 4 Tap the Line Items list to select it, and then tap the New Record button.
A new row appears in the Line Items list with the Line # and Status fields completed.
- 5 Complete the fields for the line item.
Repeat the previous step to add additional line items.

NOTE: Beginning with Siebel Handheld version 7.8, pricing changes are not applied until after you have synchronized with the server (for Direct Server Sync) or Mobile Web Client (for Companion Sync). Any changes to the Product, Part #, Price List, Discount %, and Qty fields will clear the price fields.

After synchronizing, the Totals field is updated with the Quantity Requested total, and the Order record Item Total and Total fields are updated based on the sum of the Line Item Start Price and Net Price fields, respectively.

Entering Terms and Totals in Sales Handheld

After completing the line items, navigate to the Order Terms view to enter shipping and payment information for the order.

To add terms and totals

- 1 Navigate to the Orders screen.
The My Sales Orders list appears.
- 2 In the My Sales Orders list, select the order.
- 3 From the Show drop-down list, select Order Terms.
- 4 In the Order Terms view, tap the Terms form to select it.
- 5 In the Terms form, complete the necessary fields (such as Payment Terms, Ship Carrier, and so on).

NOTE: The default Sales Handheld configuration does not include detailed shipping and billing fields. These fields are based on different business components and can be configured as required.

Tracking Expenses in Sales Handheld

You can track expenses and create expense reports using Siebel Sales Handheld.

The following expense management procedures are included in this section:

[“Creating an Expense Report in Sales Handheld” on page 142](#)

[“Submitting an Expense Report in Sales Handheld” on page 143](#)

Creating an Expense Report in Sales Handheld

You can create expense reports in Siebel Sales Handheld, then upload them to your server at the time of sync.

To create an expense report

- 1 Navigate to the Expenses screen.
The My Expense Reports list appears.
- 2 Tap the New Record button, and complete the necessary fields for the new record.
- 3 From the Show drop-down list, select More Info to view additional fields.

NOTE: You must complete the Submit To field or you will get an error message and your expense report will not be saved.

To add detailed line items

- 1 Navigate to the Expenses screen.
- 2 In the My Expense Reports list, locate the expense report record.
- 3 From the Show drop-down list, select Expense Items.
- 4 In the Expense Report Line Items view, tap the Line Items list, and then tap the New Record button.
- 5 In the new row, complete the necessary fields for the line item.

You can not enter Line Items whose Start or End Date is outside of the Expense Report period.

NOTE: Siebel Sales Handheld Expense Reports functionality does not currently support the Mileage expense type or detailed Hotel expense tax itemization. If these expense types are required, you must enter these items using the desktop Siebel Sales application.

- 6 Repeat the previous steps to add line items.

The cumulative total of all expense line items is automatically displayed in the Totals field.

Submitting an Expense Report in Sales Handheld

After creating an expense report, you will then need to submit it for approval.

To submit an expense report

- 1 Navigate to the Expenses screen.

The My Expense Reports screen appears.

- 2 Select the desired expense report, then tap the Status field, and select submitted from the drop-down list.

The next time you sync to your enterprise system, the expense report will be submitted.

A

Troubleshooting

This appendix addresses some of the common issues faced while deploying Siebel Handheld. The appendix presents troubleshooting tips in three areas:

- Installation
- Performance
- Log Files

The audience for this appendix is Siebel database administrators, system administrators, and application administrators.

- ["Installation" on page 145](#)
- ["Synchronization" on page 146](#)
- ["Log Files" on page 148](#)
- ["SQLTrace" on page 151](#)
- ["End User Error Messages" on page 151](#)
- ["Web Server Timeout Errors" on page 151](#)
- ["Handheld Device Timeout Errors" on page 152](#)
- ["Performance" on page 152](#)

Installation

Siebel Handheld supports a specific and limited set of devices, handheld OS, desktop OS, server OS, server databases, and languages. This range of devices and platform support varies widely across the range of Siebel Handheld releases and must be carefully checked to confirm support. See *System Requirements and Supported Platforms* on Siebel SupportWeb for your Siebel application for information on supported Handheld OS, desktop OS, server OS, and server databases.

Client Installation, Backup, and Restore

If you encounter problems while installing the Siebel Handheld application on client devices from a desktop PC, refer to the following checklist. Most installation problems are covered by this checklist.

- Confirm that the device is certified and supported. Refer to *System Requirements and Supported Platforms* on Siebel SupportWeb.
- Confirm that the device has 64 MB or higher of RAM with the majority of it available for the Siebel Handheld application.
- Make sure an ActiveSync connection is running (green icon). If not, check your computer to make sure that the serial or USB port is activated and functioning correctly.

- If previous versions of Siebel Handheld were installed on the device, make sure you uninstall the application. See [“Uninstalling the Siebel Handheld Application” on page 106](#).

Siebel Handheld binaries may also be installed to a CompactFlash card to conserve (RAM) memory. The application will still be loaded into memory when it executes. To install on the CompactFlash card, set the ApplicationBinariesLocation and ApplicationDataLocation parameters in the setup.ini file. See [“Setting Up Siebel Handheld Application Installation on a CompactFlash Card” on page 91](#).

Siebel Handheld (application only - no data) may also be copied onto a CompactFlash card to aid in deployments. The initial backup image should be made of a device that has *not* done an initial synchronization. An initial synchronization will still be required by each user to receive the configuration and data. For information on backup utilities, see the documentation accompanying your handheld device.

It is also possible to back up Siebel Handheld on a PC using the Backup/Restore feature within ActiveSync.

Synchronization

Synchronization problems can be caused by incorrect settings in the Siebel Handheld setup.ini or .cfg files. Be sure that application names, data sources, and .srf files are correct.

Make sure to set the SyncURL setting in the client setup.ini file for all synchronization methods. Also, be sure to grant the user visibility to these views in the Administration - Application > Responsibilities view.

NOTE: Check the log files and confirm the accuracy of the generated connect string.

Companion Sync Checklist

Use the following list to troubleshoot problems you encounter using Companion Sync.

- Is the latest version of ActiveSync (version 3.5 or later) installed and running?
- Is ActiveSync connected (green icon)?
- Do you have the correct data source defined in the handheld .cfg file?
- If you have problems logging in, check to make sure that you can use the same credentials to log into the desktop client.
- Remember to keep a 1:1 ratio of users to devices. Only a single user may log in to sync each device. Failure to do so causes data corruption.

When using a SRF with a custom configuration and the sync error occurs during initialization, follow the steps below to troubleshoot problems:

To troubleshoot Companion Sync configuration errors

- 1 Add HandheldSyncLogLevel = 5 to the [pda] section in the .cfg and look for more error details in the CompSync log.

- 2 Use the Validate function in Siebel Tools to look for a configuration error.
- 3 Remove handheld views from user responsibility until synchronization passes the error point.
- 4 Remove DefaultBusObjs from Administration - Mobile > Application Administration > Settings until synchronization passes the error point.

Direct Server Sync Checklist

Use the following checklist to troubleshoot problems you encounter using Direct Server Sync.

- Did you install all client and server components successfully?
- Is there a PDA object manager (OM) running on the Siebel Server?
- Did you bounce the IIS, SWE, and Siebel Server after installation?
- Do you have network access to the URL for DSS? Can you ping the IIS server from inside and, if applicable, from outside the firewall?
- Can you successfully run a SWE command?
- Do you have the correct SyncURL defined in the setup.ini file?
- Is the network connection working from the device? Try Pocket Internet Explorer.
- If you have problems logging in, check to make sure that you can use the same credentials to log into the desktop client.
- Remember to keep a 1:1 ratio of users to devices. Only a single user may log in to sync each device. Failure to do so causes data corruption.

When using a SRF with a custom configuration and the sync error occurs during initialization, follow the steps below to troubleshoot problems:

To troubleshoot Direct Server Sync configuration errors

- 1 Turn on Handheld Sync logging to 5 and look for more error details in the Siebel Handheld Synchronization OM log. For more information, see ["Configuring Direct Server Sync Logging Levels" on page 82](#).
- 2 Use the Validate function in Siebel Tools to look for a configuration error.
- 3 Remove handheld views from user responsibility until synchronization passes the error point.
- 4 Remove DefaultBusObjs from Administration - Mobile > Application Administration > Settings until synchronization passes the error point.

Re-synchronizing Problems

Generally if, for whatever reason, synchronization is terminated, the end user is prompted with a message and the synchronization process ends. In this situation the synchronization session is allowed to close. However, if the connection with the server is unintentionally broken, the session may not have a chance to close before the connection is broken. Therefore, if the end user tries to immediately synchronize again, he may get an error message and may not be able to synchronize. Should this occur, the end user should wait for a period of time (generally, 15 minutes) to allow the session to time out and terminate. Once the session terminates, the end user should be able to synchronize again.

Log Files

This section includes the following topics:

["Direct Server Sync Log and Output Files" on page 148](#)

["Companion Sync Log and Output Files" on page 149](#)

["Handheld Device Log" on page 149](#)

Direct Server Sync Log and Output Files

The name of the Direct Server Sync Log is the OM name plus the task ID for that log session. The log is found in the log subdirectory under the Siebel root directory. Depending on the amount of detail enabled, this file can give a good perspective of what has happened during synchronization regarding the Siebel OM.

To assist Siebel Technical Support, collect the following files when logging a Siebel Handheld service request. The following files are found on the machine where Siebel Server is installed:

- All server sync user files in the *Siebel Root\siebsrvr\hhsync\application directory\user id\node id* directory.
- Server application event log extract.
- Server system event log extract.
- All files in the *Siebel Root\siebsrvr\log* directory including *CompName_task.log*.
where *CompName* is the name of an application server component, and *task* is a Siebel task number. Each sync session is assigned a new Siebel task, so there will be many of these. An example "CompName" value is "SalesCE_enu" (note that language is part of the component name itself).
- All files from all subdirectories under the *Siebel Root\siebsrvr\logarchive* directory.
- Server perfmon log files (showing memory, network, disk performance), if available.

The following files are found on the machine where the Web Server (that is, IIS) is installed:

- SWE log files from *Siebel Root\eappweb\log* (all files).

- IIS server application event log extract.
- IIS server system event log extract.
- IIS server perfmon log files (showing memory, network, disk performance), if available.

Companion Sync Log and Output Files

The name of the Companion Sync Log is compsync.log. It is found in the log subdirectory under the Siebel root directory. Depending on the amount of detail enabled, this file can give a good perspective of what has happened during synchronization regarding the Siebel object manager.

- *Siebel Root\client\hhsync\application directory\user id\node id* directory.
- NT application event log extract.
- NT system event log extract.
- All files in the *Siebel Root\client\log* directory.
- Perfmon log files (showing memory, network, disk performance), if available.

Handheld Device Log

The siebel_log.txt file is found in the /Program Files/Siebel Handheld directory on the handheld device. It is controlled by reg key DefaultLogLevel, with values 0-4. For more information on values, see ["Siebel Handheld setup.ini Parameters" on page 87](#).

The default value of the reg key during installation is 2. This file logs all of the following:

- Database objects that were imported during synchronization.
- All SQL statements generated by the application. You must set a parameter in the setup.ini file to turn this log on. DefaultLogLevel=3 and 4 will log SQL statements to the device log. See ["Siebel Handheld setup.ini Parameters" on page 87](#) for more information about setting the parameter.
- All system error messages. You must set a parameter in the setup.ini file to turn this log on. DefaultLogLevel=4 will give the most detailed log with debug info. See ["Siebel Handheld setup.ini Parameters" on page 87](#) for more information about setting the parameter.
- All of the messages displayed on the Sync Manager dialog box as well as some basic information about synchronization, such as data source and connect string. You can set the logging level for this file using the DefaultLogLevel parameter in the setup.ini file.

Logging Handheld Synchronization Errors

Siebel Handheld Sync logs all the strings that the user sees in the sync message window as well as many informational messages that do not get displayed in the UI. These informational messages are used to help track down where an error occurred. Siebel Handheld Sync determines which messages get logged based on a value stored in the registry under the key `DefaultLogLevel`. The values range from 0 to 4; 0 logs all error messages and strings that the user sees, and 4 logs all data that Siebel Handheld Sync sends and receives.

If Siebel Handheld Sync fails, check the `siebel_log.txt` file immediately after the failure. If you need more detail, increase the logging level of `DefaultLogLevel` and run Siebel Handheld Sync again. For more information on changing `DefaultLogLevel`, see ["Siebel Handheld setup.ini Parameters" on page 87](#).

You can determine when and where an error occurs during handheld synchronization by referring to `siebel_log.txt` and the Handheld Sync Object Manager log.

The device log, `siebel_log.txt`, shows the last HTTP command that was sent to server, for example, `ExecuteLogin`, `Init`, `ProcessTransactionEx`, `ExtractDB`, and so on. The Handheld Sync Object Manager log receives the request and invokes the corresponding method.

For example, in the device log (`siebel_log.txt`), the following indicates that the device is sending an "Init" request to server:

```
INFO0x6F46107E03/30/2005 16:58:27http ://PPP_PEER:2323/salesce/
start.swe?SWEExtSource=siebelpda&SWEExtCmd=Init&PatchLevel=7.7.2.2PDA%5b18356_1]
8.471262E-309NU&SyncFormat=CE0&SyncNodeId=&TimeStamp=1112230707
```

```
INFO0x6F46107E03/30/2005 16:59:20<Init ReturnCode="OK" Complete="100">
```

or, for Sales SIA

```
INFO0x6F46107E03/30/2005 16:58:27http ://PPP_PEER:2323/siasalesce/
start.swe?SWEExtSource=siebelpda&SWEExtCmd=Init&PatchLevel=7.7.2.2PDA%5b18356_1]
8.471262E-309NU&SyncFormat=CE0&SyncNodeId=&TimeStamp=1112230707
```

`INFO0x6F46107E03/30/2005 16:59:20<Init ReturnCode="OK" Complete="100">`The server log (Handheld Sync OM log, that is, `CompNameObjMgr_enu_xxxxx.log`), shows that the "Init" request is received by the server and the "Init" method is invoked:

```
ObjMgrBusServiceLogInvokeMethod402005-03-23 10:45:27Begin: Business Service
'Handheld Synchronization' invoke method: 'Init' at 10c2bc68
```

```
HandheldSyncLogDebug502005-03-23 10:45:27Request Init received
```

(Where "CompName" is the server component name of the handheld synchronization for the specific handheld application.)

In addition to the device log, customers should also check the `CompSync` log in laptop (for Companion Sync) or `SalesCEObjMgr_enu_xxxxx.log` in Siebel Server (for DSS). For more information on changing logging levels, see ["Configuring Direct Server Sync Logging Levels" on page 82](#) and ["Configuring Companion Sync Logging Levels" on page 83](#).

SQLTrace

Use SQLTrace for diagnostic purposes if you encounter serious configuration errors or performance problems and cannot otherwise diagnose the problem. The problem may quickly become apparent in the log entries from SQL tracing.

To enable SQL tracing

- 1 Log into srvrmgr prompt.
- 2 At the DOS prompt, run server manager (srvmgr) from the <siebsrvr/bin> directory:
srvmgr /g gateway /e enterprise /u sadmin /p sadmin
- 3 Run: change evtloglvl ObjMgrSqlLog=4 for comp [OMName], where [OMName] = the OM name (for example, SalesCEObjMgr_enu).
- 4 Log entries are written as described in [“Log Files” on page 148](#).

CAUTION: When SQL tracing is enabled, synchronization is severely and adversely affected. Therefore, it is recommended that you turn SQL tracing on for a limited time to diagnose a specific problem, then turn SQL tracing off.

End User Error Messages

In addition to errors found in the siebel_log.txt file, you might receive a Transaction Errors Reported message during synchronization. These errors are logged in TXNError.hh. The message appears on the handheld device in the Syncmanager Status box. You can double-click the message at any time to see the errors.

You can make the following settings in setup.ini:

TXNErrorLevel = 0 (no log information)

TXNErrorLevel = 1 (report txn errors in the client)

For more information on end-user messages, see [“Synchronization Troubleshooting with the Siebel Handheld Client” on page 120](#).

Web Server Timeout Errors

If synchronization times are long due to the size of the database file or the speed of the network connection, your end users may encounter Web server timeout errors and synchronization failures. First try to resolve this problem by reducing the size of your extract and configuring your server performance. You can reduce the size of the extract by fine-tuning filters, or if appropriate filters have already been defined, select ones that will return less data. If after doing this, your end users continue to experience timeout errors, then increase the timeout parameter on IIS for the default Web Server.

Follow the procedure for your platform to change the timeout parameter.

To change the timeout parameter on Windows

- 1 From the Start menu, select Programs > Administrative Tools > Internet Services Manager.
- 2 From the Internet Information Services window, select the local machine, right-click on the Default Web Site, and select Properties from the pop-up list.
- 3 From the Web Site Properties window, select the Web Site tab.
- 4 Under the Connections heading, locate the Connection Timeout property and increase the number of seconds.
- 5 Click OK.

Handheld Device Timeout Errors

The following three parameters are stored in device registry. They control the device timeout. For more information on device timeout errors, see the following parameters in ["Siebel Handheld setup.ini Parameters" on page 87](#):

- InternetOptionReceiveTimeout = 600000
- InternetOptionSendTimeout = 600000
- InternetOptionDataExtractionTimeout = 600000

Performance

This section discusses ways you can optimize your client performance, server performance, and network performance.

Client Performance

Client performance is affected primarily by the device capability (minimum 206 MHz processor and 64 MB RAM), configuration, and the quantity of data loaded onto the device. In general, screen-to-screen and view-to-view navigation times of 3 to 4 seconds or less should be considered normal.

It is strongly recommended that customers follow these general guidelines to optimize the performance of their handheld applications:

- Keep configuration under 30 views.
- Keep RML file size under 1.75 MB.
- Keep database files (dbfile.txt) under 2 MB.
Use filters as outlined in the Siebel 2000 Handheld Synchronization Technical Note.
- Keep the number of records for each business component under 2,500.
- Avoid installing other applications on the device at the same time.
- Users should synchronize their data frequently.

Additional configuration information can be found in the Siebel Technical Note 405.

The Siebel Handheld client will benefit from periodic closing and restarting the application to release memory consumed by the handheld operating system. Use File > Exit in the menu to exit from the Siebel Handheld application.

If an external VGA driver is or has been loaded on the device in the past and is no longer needed, be sure to unload it, because it is known to have significant performance impacts on handheld devices.

Server Performance

Server performance affects the performance and scalability of Direct Server Sync processes. Customers should engage Expert Services to do a Scalability Review. The following guidelines are general in nature and pertain to the Siebel Handheld Sync components running on a Siebel Server:

- Use Performance Monitor to track memory and processor performance on the Siebel server.
- Make sure that the Servers (IIS, GW, OM and DB) are on the same high speed LAN segment.
- Siebel Handheld Sync components will stress Siebel Server and database performance because of the intensive interactions during large concurrent synchronizations.
- Estimate that 64 MB is used per Siebmtsh.exe instance.
- To calculate the theoretical maximum concurrent users:
 - $\text{Numusers} = \text{Server_Memory} * \text{threads_per_process_ratio} / 64 \text{ MB}$.
- Optimize the Threads per Process Ratio (Max Tasks/Max MT Servers) per Technical Note 405.
- Set Max Tasks=Max. number of concurrent users (for example, 150).
- Set MinMTServers=MaxMTServers (for example, 30 for 5:1 ratio, if this is determined to be appropriate).

To optimize and tune a Siebel DB server:

- Use Performance Monitor to track memory and processor performance on the DB server.
- Turn on SQL tracing and search for long-running SQL calls.
- Estimate 64 MB of RAM for each concurrent user.
- Consider creating indexes to tune the queries (only performed with the assistance of Siebel Expert Services).
- Consider using a RAID 0+1 disk array with an expanded number of spindles to optimize database performance.

NOTE: Make sure that DB Server settings are set to recommended values. Timeouts should be set at the Siebel Server. Be careful that the timeout is set longer than the longest SQL query.

Network Performance

The condition of the network affects Direct Server Sync performance and scalability. In general, a low-latency, high-bandwidth network is preferred with dedicated rather than shared network connections. The following are general network considerations:

- Make sure there is adequate bandwidth throughout the entire round-trip of network packets and estimate where bottlenecks will occur due to high concurrent load. For example, if 50 users are concurrently synchronizing 1 MB each, 50 MB of data must pass through the network. If this data is passing through a single leased 56 KB per second line, then this data will minimally take $500,000 \text{ KB} / 56 \text{ KB/sec} = 8928 \text{ seconds} = 148 \text{ minutes}$. In reality, a 56 KB per second line will offer only 30-40 KB per second average throughput, which causes further bandwidth constraints. Check the total available bandwidth of network providers (private or public ISP).
- Verify that you have low latency lines with ping round trips of less than 1 second (1000 ms) with no dropped packets.
- Verify if roundtrips occur with less than 10 hops.
- Check the actual throughput of network connections by performing simple file transfers with no Siebel software.
- VPN software from third parties accounts for 30 to 60 percent of additional packet overhead because of the encryption.

Network problems can usually be resolved by working with network providers to size network connections and optimize network routing. Consider the use of burst networks, quality of service contracts, private networks, and dedicated modem banks directly into a high-speed LAN environment.

B

Screens and Views

Siebel Handheld Client supports a subset of the screens and views supported by the Siebel Web Client application. Other screens and views can be configured for your Siebel Handheld Client application if they are based on currently supported classes. Application developers and application administrators will find the information in this appendix useful.

If you configure screens and views based on unsupported classes, you may see anomalous results. For information on how to determine the classes used by other screens and views, see *Object Types Reference*.

Screens and Views

The screens and views shipped with the Siebel Sales Handheld sample application are shown in [Table 31](#).

Table 31. Siebel Sales Handheld Screens and Views

Screen	View Name on UI	View Name in Siebel Tools (salesce.cfg)
Contacts	My Contacts	SHCE Sales Visible Contact List View
	More Info	SHCE Sales Contact Details View
	Personal Contacts	SHCE Sales Personal Contact List View
	Opportunities	SHCE Sales Contact Detail - Opportunities View
Accounts	My Accounts	SHCE Sales Account List View
	My Team's Accounts	SHCE Sales Manager's Account List View
Accounts	More Info	SHCE Sales Account Detail View
	Activities	SHCE Sales Account Detail - Activities View
	Contacts	SHCE Sales Account Detail - Contacts View
	Addresses	SHCE Sales Account Detail - Business Address View
	Opportunities	SHCE Sales Account Detail - Opportunities View
	Opportunities	My Opportunities
My Team's Opportunities		SHCE Sales Manager's Opportunity List View
More Info		SHCE Sales Opportunity Detail View

Table 31. Siebel Sales Handheld Screens and Views

Screen	View Name on UI	View Name in Siebel Tools (salesce.cfg)
	Activities	SHCE Sales Opportunity Detail - Activities View
	Contacts	SHCE Sales Opportunity Detail - Contacts View
	Quotes	SHCE Sales Opportunity Quote View
	Products	SHCE Sales Opportunity Detail - Products View
Employees	All Employees	SHCE Sales Employee List ReadOnly View
	Employees - More Info	SHCE Sales Employee Detail View
Calendar	Daily	SHCE Sales Calendar Daily View - My
	Weekly	SHCE Sales Calendar Weekly View - My
	Monthly	SHCE Sales Calendar Monthly View - My
	Employee Participants	SHCE Sales Calendar Employee Participants View
	Contact Participants	SHCE Sales Calendar Contact Participants View
	Note: This view does not have a view name in the UI. It is a drill-down view.	SHCE Sales Calendar Add/Modify View
Activities	My Activities	SHCE Sales Activity List View
	More Info	SHCE Sales Activity Detail View
	Contacts	SHCE Sales Activity Contact Participants View
	Employees	SHCE Sales Activity Employee Participants View
Expense Reports	My Expense Reports	SHCE Sales Expense List View
	More Info	SHCE Sales Expense List Detail View
	Expense Items	SHCE Sales Expense Item List View
Quotes	My Quotes	SHCE Sales Quote List View
	More Info	SHCE Sales Quote List Detail View
	Quote Items	SHCE Sales Quote Detail View
	Orders	SHCE Sales Quote Orders View
Orders	My Sales Orders	SHCE Sales Order Entry - My Orders View (Sales)
	More Info	SHCE Sales Order Entry - Detail Orders View (Sales)
	Line Items	SHCE Sales Order Entry - Line Items View (Sales)

Table 31. Siebel Sales Handheld Screens and Views

Screen	View Name on UI	View Name in Siebel Tools (salesce.cfg)
	Order Terms	SHCE Sales Order Entry - Order Terms View (Sales)
Products	All Products	SHCE Sales Product List View
	More Info	SHCE Sales Product Detail View
Pricing	Price Lists	SHCE Sales Price List View
	More Info	SHCE Sales Price List Detail View
	Line Items	SHCE Sales Price List Line Item View

C

Business Components and Classes

Siebel Handheld Client supports a subset of the business components and classes supported by the Siebel Web Client application. This appendix lists the supported business components, business component classes, and applet classes.

- ["Supported Business Components for Siebel Handheld" on page 159](#)
- ["Business Component Classes" on page 160](#)
- ["Applet Classes" on page 161](#)

Supported Business Components for Siebel Handheld

[Table 32](#) lists the supported business components for Siebel Sales Handheld.

Table 32. Siebel Sales Handheld Business Components

Supported Business Components
Account
Action
Business Address
Contact
Contact (All)
Contact (Personal)
Employee
Employee (MM)
Expense
Expense Item
Internal Product
Opportunity
Opportunity Product
Order Entry - Line Items
Order Entry - Orders

Table 32. Siebel Sales Handheld Business Components

Supported Business Components
Price List
Quote
Quote Item

Business Component Classes

NOTE: The business component classes for the handheld application are based on the classes for the Web Client. However, in most instances, because of the limitations of the handheld, only the subset of the class functionality that is required for the handheld is supported.

Table 33 lists the supported business component classes for Siebel Sales Handheld.

Table 33. Siebel Sales Handheld Business Component Classes

Supported Business Component Classes
CSSBCActivity
CSSBCBase
CSSBCBCExpitm
CSSBCExprpt
CSSBCLineItem
CSSBCOppty
CSSBCOrder
CSSBCPriceList
CSSBCProdBuyNow
CSSBCProdRev
CSSBCQuote
CSSBCQuoteItem
CSSBCUser

Applet Classes

You may create additional screens and views for your handheld application. Any new screens and views must be based on classes and business components that are supported for the Sales Handheld application. Refer to [Table 34](#) for the supported applet classes.

Table 34. Siebel Sales Handheld Applet Classes

Supported Applet Classes
CSSFrame
CSSFrameAlarmList
CSSFrameBase
CSSFrameCECaAddModify
CSSFrameCEGridDay
CSSFrameCEGridMonth
CSSFrameCEGridWeek
CSSFrameCEHome
CSSFrameCEMultiPart
CSSFrameList
CSSFrameListBase
CSSFrameListExpitm
CSSFrameListQuote
CSSFrameListQuoteItem
CSSFrameQuote

D

User Properties and Methods

This appendix documents the handheld-specific user properties and methods for the Siebel Handheld application.

User Properties

Table 35. User Properties

Name	Comments
HandheldSyncPickMode	User property on a field of a business component. When set to NoFail, turns Extended Pick processing ON. See "Enabling Extended Pick Processing in Siebel Handheld" on page 98 for more information.
HandheldSyncInsertMode	User property on a business component. When set to FailOnError, enables insert failure processing. See "Insert Failure Processing in Siebel Handheld" on page 100 for more information.
OverridePopupVisibility	Overrides Popup Visibility Type on a business component. Use OverridePopupVisibility to change the visibility on a picklist without changing the Popup Visibility Type. See "Overriding the Popup Visibility" on page 76 for more information.
View	Used with the GotoView method. Specifies the view to be displayed when navigating from one view to another. See "Applet Focus Behavior" on page 24 for more information.

Methods

The following details methods you can use for your Siebel Handheld application.

AutoQuote

The AutoQuote method generates a quote from an opportunity. The opportunity may contain one or more products. A quote item is generated for each product in the opportunity that has the AutoQuote field flag selected.

When the AutoQuote method is executed, the quote business component fields are populated with the values shown in [Table 36](#).

Table 36. AutoQuote Method

Field	Value
Quote Number	This field is assigned a system-generated value
Revision	1
Name	Quote Number (or user-provided name)
Opportunity	Opportunity from which AutoQuote was called
Account	Opportunity's account
Account Location	Opportunity's account location
Status	In Progress
Active	Flag is set to on
Currency	Opportunity's currency code
Price List	Opportunity's price list
Sales Rep	User's login
Start Date	Today's date
End Date	Today's date + 30 days (30 days is determined by the QUOTE_EXPIRATION_PERIOD LOV)

The Quote Item business component fields are populated from the corresponding Opportunity Product's business component fields as shown in [Table 37](#):

Table 37. Population of Fields in Quote Item View

Source Field From Opportunity Product View	Destination Field Quote Item View
Product	Product
Product Quantity	Extended Quantity Requested
Write-In Product (Not exposed)	Write-In Product (Not exposed)
Expected Delivery Date	Requested Delivery Date (Not exposed)
ID (Not exposed)	Opportunity Product ID (Not exposed)

Fields that are noted as “Not exposed” do not appear in the user interface.

In addition, the Quote Number field in the generated quote is copied back to the Opportunity Product view ([Table 38](#)).

Table 38. Population of Fields in Opportunity Product View

Source Field From Quote View	Destination Field To Opportunity Product View
Quote Number	Quote Number (Not exposed)

AutoOrder

The AutoOrder method generates an order from a quote. AutoOrder creates a corresponding line item for each quote item in the quote. The Order Entry Line Items business component fields are populated with the corresponding Quote Item business component fields as shown in [Table 39](#).

Table 39. Population of Fields in Order Entry - Line Items View

Source Field From Quotes – Quote Items View	Destination Field To Order Entry - Line Items View
Extended Quantity Requested	Extended Quantity
Product	Product
Discount Amount (Not exposed)	Discount Amount (Not exposed)
Discount Percent	Discount Percent (Not exposed)
Description (Not exposed)	Description (Not exposed)
Requested Delivery Date (Not exposed)	Due Date (Not exposed)
Unit Price (Not exposed)	Unit Price (Not exposed)
Volume Discount Id (Not exposed)	Volume Discount Id (Not exposed)
Volume Discount Item Id (Not exposed)	Volume Discount Item Id (Not exposed)
Base Price	Base Price
Adjusted List Price	Adjusted List Price
Covered Product Id (Not exposed)	Covered Product Id (Not exposed)

If the quote item’s product is a service product, then the following fields are also copied from the Quotes – Quote Items view to the Order Entry - Line Items view (Table 40).

Table 40. Copied Fields for Service Products

Source Field From Quote – Quote Items View	Destination Field To Order Entry - Line Items View
Covered Quote Item Id (Not exposed)	Covered Quote Item Id (Not exposed)
Service Price Amount (Not exposed)	Service Price Amount (Not exposed)
Service Price Percent (Not exposed)	Service Price Percent (Not exposed)
Service Price Method (Not exposed)	Service Price Method (Not exposed)

When AutoOrder is executed, the quote’s Status field is updated to “Order Placed.”

When AutoOrder is executed, the following fields in the Order Entry - Orders business component are pre-populated (automatically populated?) as shown in Table 41.

Table 41. Pre-populated Fields in Order Entry - Orders Business Component

Order Entry - Order Business Component Field	Value
Order Number	System-generated value
Account	Quote’s Account
Account Location	Quote’s Account Location
Contact Last Name	Quote’s Contact Last Name
Contact First Name	Quote’s Contact First Name
Order Priority	Medium
Status	Pending
Order Type	Sales Order
Active	Set to Active (Turned on? Flag is set to on?)
Order Date	Today’s date
Discount	Quote’s Discount
Price List	Quote’s Price List
Currency Code	Quote’s Currency Code
Requested Ship Date	Quote’s Requested Ship Date (Not exposed)
Created	Today’s date
Created By Name	User’s login ID

Table 41. Pre-populated Fields in Order Entry - Orders Business Component

Order Entry - Order Business Component Field	Value
Discount Amount (Not exposed)	Quote's Discount Amount (Not exposed)
Primary Organization Id (Not exposed)	Quote's Primary Organization Id (Not exposed)

E

Print Tagging Language

This chapter describes the print tagging language that is used to create print templates for your handheld device.

The audience for this appendix is Siebel application developers.

["Overview of Siebel Handheld Print Tagging Language" on page 169](#)

["Using Variables in Print Templates" on page 185](#)

Overview of Siebel Handheld Print Tagging Language

You can create the print template file in any text editor.

- Tags are enclosed in angle brackets and identified with the keyword TAG, followed by a colon.
For example: <TAG:>
- Parameters are specified with a keyword, followed by an equals sign. Arguments are in uppercase, surrounded by quotation marks.
For example, Font = "FONT FACE"
- Values are in uppercase and lowercase, surrounded by quotation marks.
For example: Font = "Helvetica"
- Tags may appear in any order in the file. The only required tag is the Title tag.
- Variables within a print template must be uniquely named. Variable names must be one-word strings and spaces are not allowed.

The following tags are used to specify the format of the print output, which applets are included, and the query that is executed:

- Applet—Specifies which applets are used in the document.
- Comment—Adds comments that do not appear in the final document.
- Divider—Adds visual lines to visually separate different parts of the document.
- Footer—Adds information such as page numbers, date, and time.
- Format—Specifies characteristics such as font, boldface, italics, and underline.
- Header—Adds information such as page numbers, date, and time.
- Page Break—Specifies a break in the text, forcing the text that follows to appear on the next page.
- Picture—Adds graphic images to the document.

- Title—Specifies a name for the template that appears in the print job list.

In addition, you may add static text in the print template.

The following print tags allow you to calculate additional information and add it to your reports:

- GetTotal—Calculates the total for a column of data.
- GetField—Gets the value of a field.
- GetCount—Calculates the number of records.

You can also calculate dates and times using the GetDate and GetTime tags, and you can retrieve the value of the registry using GetRegistry.

All of this information is stored in variables that you specify. In addition, you can assign any value to a variable using the SetVariable tag. You can present this information in your report using the Cell and EndofLine tags to create tables of information. See [“Using Variables in Print Templates” on page 185](#) for an example of how variables can be used to present information in print templates.

Applet

Description

Specifies the applet to be printed.

Usage

Any data that appears in your document must be generated from the applets in the view. Therefore, you must create applets that will produce the data required for your document.

Use the Applet tag to specify any number of list or form applets within the template and to locate the applet in your document. In the form view, a maximum of two fields per row are supported.

Syntax

```
<TAG:Applet Name="APPLET NAME" Query="QUERY STRING" Caption="CAPTION"  
Headerdivider="HEADERDIVIDER" Recorddivider="RECORDDIVIDER" Wrap="WRAP">
```

Parameter	Description
TAG:Applet	(Required) Applet tag indicator.
APPLET NAME	(Required) Applet name as defined in Siebel Tools.
QUERY STRING	(Optional) Specifies the query string directly set to the business component supporting the document. If the query string is not specified, the currently active query string in the view is applied to expose the relevant records.

Parameter	Description
CAPTION	(Optional) Specifies whether the captions in the form applets are suppressed. Valid values are TRUE (default) and FALSE. This parameter does not apply to list applets. Column headings in list applets are always enabled.
HEADERDIVIDER	(Optional) Specifies whether a divider is printed below the column heading in list applets. Valid values are TRUE and FALSE (default). This parameter does not apply to form applets.
RECORDDIVIDER	(Optional) Specifies whether a horizontal divider is printed between records in list applets. Valid values are TRUE and FALSE (default). This parameter does not apply to form applets.
WRAP	(Optional) Specifies whether text field values are word wrapped. Valid values are TRUE and FALSE (default). This parameter does not apply to numeric fields.

Example

<TAG:Applet Name="Order List" Headerdivider="TRUE">

Cell

Description

Prints the string stored in STRING or VARIABLE NAME at the specified location on the current line.

Usage

Use the Cell tag to create cells of data in a row in a table. Use it with the EndOfLine tag. If the data exceeds the width of the cell specified by Startat and Endat, it wraps to the next line.

Syntax

<TAG:Cell Startat="START" Endat="END" Name="STRING" Variable="VARIABLE NAME" Align=ALIGNMENT">

Parameter	Description
TAG:Cell	(Required) Required tag indicator.
START	(Required) Specifies the starting point of the cell, expressed as a percentage of the printable page width. For example, if START =10, then the cell starts at the point that is 10% from the left edge of the printable width.
END	(Required) Specifies the end point of the cell, expressed as a percentage of the printable page width. For example, if END=50, then the cell ends at the point that is 50% from the left edge of the printable width.
STRING	(Optional) String value. If Variable is not specified, then String is a required parameter.
VARIABLE NAME	(Optional) Name of variable where the value is stored. If String is not specified, then Variable is a required parameter.
ALIGNMENT	(Optional) Specifies the alignment of the string. Valid values are LEFT (default), CENTER, and RIGHT.

Example

```
<TAG:Divider Weight="3" Startat="20" Endat="80">
<TAG:Cell Startat="0" Endat="50" name="TOTAL:" Align="RIGHT">
<TAG:Cell Startat="50" Endat="100" Variable="vvv1total" Align="RIGHT">
<TAG:EndOfLine>
<TAG:Cell Startat="0" Endat="50" name="TOTAL Defective:" Align="RIGHT">
<TAG:Cell Startat="50" Endat="100" Variable="vvvDefectiveTotal" Align="RIGHT">
<TAG:EndOfLine>
<TAG:Cell Startat="0" Endat="50" name="TOTAL Good:" Align="RIGHT">
<TAG:Cell Startat="50" Endat="100" Variable="vvvGoodTotal" Align="RIGHT">
<TAG:EndOfLine>
<TAG:Cell Startat="0" Endat="50" name="Defective Count:" Align="RIGHT">
<TAG:Cell Startat="50" Endat="100" Variable="vvvDefectiveCount" Align="RIGHT">
<TAG:EndOfLine>
<TAG:Cell Startat="0" Endat="50" name="Good Count:" Align="RIGHT">
```

```
<TAG:Cell Startat="50" Endat="100" Variable="vvvGoodCount" Align="RIGHT">
<TAG:EndOfLine>
<TAG:Cell Startat="50" Endat="100" Variable="vvv3reg">
<TAG:EndOfLine>
<TAG:Cell Startat="50" Endat="100" Variable="vvv5str">
<TAG:EndOfLine>
<TAG:Cell Startat="0" Endat="30" Variable="vvv4date">
<TAG:Cell Startat="30" Endat="70" Variable="vvv4longdate">
<TAG:Cell Startat="70" Endat="100" Variable="vvv8time">
<TAG:EndOfLine>
```

Comment

Description

Adds code comments to the print template.

Usage

Use to add explanatory notes or documentation to explain and maintain the print template. Comment tags are ignored during printing and do not appear in the printed document.

Syntax

```
<REM: COMMENT>
```

Parameter	Description
REM	(Required) Comment tag indicator.
COMMENT	(Optional) Comment text.

Example

```
<REM: Quotation Print Template. This template includes four applets.>
```

Divider

Description

Renders a horizontal line across the width of the page.

Usage

Use to visually separate the different sections of your document. The Divider tag can be used between other tags; therefore, you may add a line between two applets. However, you cannot embed a Divider within an applet.

Syntax

```
<TAG:Divider Weight="WEIGHT" Startat="START" Endat="END">\
```

Parameter	Description
TAG:Divider	(Required) Divider tag indicator.
WEIGHT	(Optional) Specifies line thickness. Valid values are 1–5. The default value is 1, which produces a line 0.2 mm wide. Increasing the value by 1 increases the width by 0.2 mm. A 5 produces a line that is 1 mm wide.
START	(Optional) Percentage that specifies the starting point of the line. The default is 0%, the farthest left point.
END	(Optional) Percentage that specifies the end point of the line. The default is 100%, the farthest right point.

Example

```
<TAG:Divider Weight="2" Startat="20" Endat="80">
```

EndOfLine

Description

Specifies the end of a row and advances to the next line.

Usage

Use to create rows of data in a table. Used with the Cell tag.

Syntax

```
<TAG:EndOfLine>
```

Example

```
<TAG:Cell Startat="0" Endat="50" Name="TOTAL:" Align="RIGHT">
<TAG:Cell Startat="50" Endat="100" Variable="vvv1total" Align="RIGHT">
<TAG:EndOfLine>
```

Footer

Description

Adds footer information such as page numbers, the current date, and the current time.

Usage

You may, for example, always want the text "Thank you for your business!" to appear on the bottom of your receipts. If so, you may include this text in a Footer tag.

The Footer tag may be specified anywhere in the template file; however, it will always appear at the very bottom of your document. Only one Footer tag is applied to the document. If you have multiple Footer tags in the file, only the last Footer tag is used; any other Footer tags are ignored.

If you include a Footer tag in your template, then you must set the BottomMargin in setup.ini to a minimum of 20.

The footer has three sections, Left, Center, and Right, which are used to position the information in the footer.

The text in the footer is formatted in 10 point, Helvetica font. If Helvetica is not available on your system, the default font is used. You cannot customize text formatting of the Footer tag. The Format tag does not affect the formatting of the footer.

Syntax

```
<TAG:Footer Left="DATA" Center="DATA" Right="DATA">
```

Parameter	Description								
TAG:Footer	(Required) Footer tag indicator.								
DATA	(Optional) Static text or one of the following data tags:								
	<table border="1"> <thead> <tr> <th>Data tag</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td><page></td> <td>Page number</td> </tr> <tr> <td><date></td> <td>Date of the printing</td> </tr> <tr> <td><time></td> <td>Time of the printing</td> </tr> </tbody> </table>	Data tag	Description	<page>	Page number	<date>	Date of the printing	<time>	Time of the printing
Data tag	Description								
<page>	Page number								
<date>	Date of the printing								
<time>	Time of the printing								

Example

```
<TAG:Footer Left="<date>" Right="<page>">
```

Format

Description

Specifies the characteristics of the text—the typeface or font, whether the text is in boldface, italics, or underlined, and the text alignment.

Usage

The font specification specifies the characteristics of all text that follows the tag until the next Format tag.

The text alignment tag (Align) behaves somewhat differently. When the applet is rendered, the field alignment specification takes precedence over the Align parameter.

Syntax

```
<TAG:Format Face="FONT FACE" Size="FONT SIZE" Bold="BOLD" Italic="ITALIC"
Underline="UNDERLINE" Align="TEXT ALIGNMENT">
```

Parameter	Description
TAG:Format	(Required) Format tag indicator.
FONT FACE	(Required) Specifies the typeface of the text. Any typeface installed on the handheld device may be specified. There is no default for this parameter.
FONT SIZE	(Required) Specifies the text size. Any installed font size for an installed typeface on the handheld device may be specified. There is no default for this parameter.
BOLD	(Optional) Specifies whether the text is in bold. Valid values are TRUE or FALSE (default). If TRUE, text is set to bold.
ITALIC	(Optional) Specifies whether the text is in italic. Valid values are TRUE or FALSE (default). If TRUE, text is set to italic.
UNDERLINE	(Optional) Specifies whether the text is underlined. Valid values are TRUE or FALSE (default). If TRUE, text is set to underline.
TEXT ALIGNMENT	(Optional) Specifies the text alignment. Valid values are LEFT (default), RIGHT, and CENTER.

Example

```
<TAG:Format Face="Helvetica" Size="10">
```

GetCount

Description

Calculates the number of records in the selected rows and assigns this value to a variable.

Usage

Use GetCount to calculate the number of records and print this value in your report.

Syntax

```
<TAG:GetCount Appletname="APPLET NAME" Query="QUERY STRING" Variable="VARIABLE NAME">
```

Parameter	Description
TAG:GetCount	(Required) Required tag indicator.
APPLET NAME	(Required) Name of the applet.
QUERY STRING	(Optional) Search specification for the rows to be included in the row set. If not specified, the current search specification is used. The syntax for the query string is: Field Name Query Statement. You may specify one or more query strings separated by a vertical bar (). For example, Query="Name LIKE 'Sieb*'" Location LIKE 'H*'"
VARIABLE NAME	(Required) Name of variable where the value is stored.

Example

```
<TAG:GetCount Appletname="CS HH Product Bucket List Applet" Query="Status|Good" Variable="StatusGood">
```

GetDate

Description

Gets the current date, offsets the date by the number of days specified in Dayoffset, and stores the result in a variable.

Usage

Use GetDate to print a specific date in your report.

Syntax

<TAG:GetDate Dayoffset="NUMBER OF DAYS" Variable="VARIABLE NAME" Logformat="DATE FORMAT">

Parameter	Description
TAG:GetDate	(Required) Required tag indicator.
NUMBER OF DAYS	(Optional) Number of days by which the current date is offset. For example, -100 subtracts 100 days from the current date; 100 adds 100 days to the current date. The default is 0.
VARIABLE NAME	(Required) Name of variable where the value is stored.
DATE FORMAT	(Optional) TRUE prints the date in long date format (for example, Monday, February 11, 2002). FALSE prints the short date format (for example, 2/21/02). The default is FALSE.

Example

<TAG:GetDate Longformat="TRUE" Variable="LongDate">

GetField

Description

Gets the value of the specified column of the first row of selected rows and assigns the result to a variable.

Usage

Use GetField to print a value without developing a print applet. Design the query and sort strings so that the desired record is the first record in the selected rows. GetField only allows you to get the value in the first record.

Syntax

<TAG:GetField AppletName="APPLET NAME" Fieldname="FIELD NAME" Query="QUERY STRING" Sort="SORT STRING" Variable="VARIABLE NAME">

Parameter	Description
TAG:GetField	(Required) Required tag indicator.
APPLET NAME	(Required) Name of the applet.
FIELD NAME	(Required) Name of the field or column.
QUERY STRING	(Optional) Search specification for the rows to be included in the total. If not specified, the current search specification is used.

Parameter	Description
SORT STRING	(Optional) Sort specification. If not specified, the current sort specification is used. The syntax is: Field Name [ASC][DESC]. The default is ASC (Ascending). For example: Sort="Account DESC, Date". In the example, the Account field is sorted in descending order, then the date field is sorted in ascending order.
VARIABLE NAME	(Required) Name of variable where the value is stored.

Example

```
<TAG:GetField AppletName="CS HH Product Bucket List Applet" Fieldname="Quantity" Variable="ProdBucketListField">
```

GetRegistry

Description

Gets a value in the registry for Siebel Handheld and assigns it to a variable.

Usage

Use GetRegistry to print the contents of the registry key in your report.

Syntax

```
<TAG:GetRegistry Name="REGISTRY NAME" Variable="VARIABLE NAME">
```

Parameter	Description
TAG:GetRegistry	(Required) Required tag indicator.
REGISTRY NAME	(Required) Value the registry.
VARIABLE NAME	(Required) Name of variable where the value is stored.

Example

```
<TAG:GetRegistry Name="InstallDir" Variable="Registry">
```

GetTime

Description

Gets the current time, offsets the time by the number of seconds specified in Secondoffset, and assigns the result to a variable.

Usage

Use GetTime to print a specific time in your report.

Syntax

```
<TAG:GetTime Secondoffset="NUMBER OF SECONDS" Variable="VARIABLE NAME">
```

Parameter	Description
TAG:GetTime	(Required) Required tag indicator.
NUMBER OF SECONDS	(Optional)Number of seconds by which the current time is offset. For example, -100 subtracts 100 seconds from the current time; 100 adds 100 seconds to the current time. The default is 0.
VARIABLE NAME	(Required) Name of variable where the value is stored.

Example

```
<TAG:GetTime Secondoffset="3600" Variable="Time">
```

GetTotal

Description

Calculates the total for the specified column for all selected rows and assigns the value to a variable.

Usage

Use GetTotal to calculate a column total and display the total in your report.

Syntax

```
<TAG:GetTotal AppletName="APPLET NAME" FieldName="FIELD NAME" Query="QUERY STRING" Variable="VARIABLE NAME">
```

Parameter	Description
TAG:GetTotal	(Required) Required tag indicator.
APPLET NAME	(Required) Name of the applet.

Parameter	Description
FIELD NAME	(Required) Name of the field or column. Specify a field or column with numeric data. If you specify a field with non-numeric data, a 0 is assigned to the variable.
QUERY STRING	(Optional) Search specification for the rows to be included in the total. If not specified, the current search specification is used. The syntax for the query string is: Field Name Query Statement. You may specify one or more query strings separated by a vertical bar (). For example, Query="Name LIKE 'Sieb*'" "Location LIKE 'H*'"
VARIABLE NAME	(Required) Name of variable where the value is stored.

Example

```
<TAG:GetTotal AppletName= "CS HH Product Bucket List Applet" Fieldname="Quantity"
Variable="ProdBucketListTotal">
```

Header

Description

Adds header information such as page numbers, the current date, and the current time.

Usage

You may always want the current date and time to appear on your invoices. If so, you may include this information in a Header tag.

The Header tag may be specified anywhere in the template file; however, it always appears at the very top of your document. Only one Header tag is applied to the document. If you have multiple Header tags in the file, only the last Header tag is used; any other Header tags are ignored.

If you include a Header tag in your template, then you must set TopMargin in setup.ini to a minimum of 20.

The header has three sections, Left, Center, and Right, which are used to position the information in the header. The Left parameter aligns the text with the left margin, and the Right parameter right aligns the text with the right margin. The Center parameter centers the text in the header.

The text in the header is formatted in 10 point, Helvetica font. If Helvetica is not available on your system, the default font is used. You cannot customize text formatting of the Header tag. The Format tag does not affect the format of the header.

Syntax

<TAG:Header Left="DATA" Center="DATA" Right="DATA">

Parameter	Description								
TAG:Header	(Required) Header tag indicator.								
DATA	(Optional) Static text or one of the following data tags:								
	<table border="1"><thead><tr><th>Data tag</th><th>Description</th></tr></thead><tbody><tr><td><page></td><td>Page number</td></tr><tr><td><date></td><td>Date of the printing</td></tr><tr><td><time></td><td>Time of the printing</td></tr></tbody></table>	Data tag	Description	<page>	Page number	<date>	Date of the printing	<time>	Time of the printing
Data tag	Description								
<page>	Page number								
<date>	Date of the printing								
<time>	Time of the printing								

Example

<TAG:Header Center="Company Confidential">

Page Break

Description

Forces text that follows the tag to appear on the next page.

Usage

Use this for multipage documents or forms.

Syntax

<TAG:PageBreak>

Parameter	Description
TAG:PageBreak	(Required) Page break tag indicator.

Example

<TAG:PageBreak>

Picture

Description

Specifies graphic files included in the print template.

Usage

Use to add graphic images, such as a company logo, to your documents.

The supported file formats are BMP and JPG.

Graphics files are located in the \Program Files\Siebel Handheld\templates directory on the handheld device. Specify the full path name of the file for the Name parameter.

Scaling or graphics operations, such as inverse image, are not supported.

The Alignment and Position parameters are used together to place the graphic. Alignment specifies the left edge, the center, or the right edge of the graphic. Position is distance, specified in millimeters, from the left edge of the paper.

- If Alignment = "Left" and Position="30", then the left edge of the graphic is set 30 millimeters from the left edge of the paper.
- If Alignment = "Center" and Position = "30", the center of the graphic is set 30 millimeters from the left edge of the paper.
- If Alignment = "Right" and Position = "30", the right edge of the graphic is set 30 millimeters from the left edge of the paper.

If Position is not specified, it defaults to 0. Depending on the Alignment setting, the graphic is left-aligned (Alignment = "Left"), the graphic is right-aligned (Alignment = "Right"), or the graphic is centered (Alignment = "Center")

Syntax

```
<TAG:Picture Name="FILE NAME" Alignment="ALIGNMENT" Position="POSITION">
```

Parameter	Description
TAG:Picture	(Required) Picture tag indicator.
FILE NAME	(Required) Specifies the full path and name of the graphics file.
ALIGNMENT	(Optional) Specifies the left edge, the center, or the right edge of the graphic. Used with the Position parameter to specify the horizontal position of the graphic. Valid values are LEFT (default), CENTER, and RIGHT.
POSITION	(Optional) Specified in millimeters, it is the distance from the left edge of the paper. Used with the Alignment parameter to specify the horizontal position of the graphic. The default is 0.

Example

```
<TAG:Picture Name="\Program Files\Siebel Handheld\templates\logo.bmp" Alignment="Right" Position="88">
```

SetVariable

Description

Sets a value to a variable.

Usage

Use SetVariable to assign a value to a variable. You can then print the value by specifying the variable in the Cell tag.

Syntax

```
<TAG:SetVariable Name="VALUE" Variable="VARIABLE NAME">
```

Parameter	Description
TAG:SetVariable	(Required) Required tag indicator.
VALUE	(Required) A value.
VARIABLE NAME	(Required) Name of variable where the value is stored.

Example

```
<TAG:SetVariable="100" Variable="TotalQuantity">
```

Static Text

You may add static text anywhere in your template by using the current Format settings. The text goes across the entire page width. If it exceeds the width of the page, it wraps to the next line.

Example

This quote is valid for 60 days from the date on this quotation.

Title

Description

Name used to identify the template.

Usage

The Title tag is a required tag in your print template file.

When you print your document, this title appears in the print job list. This title does not appear on the document that is printed. Use static text to add the document title to your template.

Syntax

<TAG:Title Title="TITLE">

Parameter	Description
TAG:Title	(Required) Title tag indicator.
TITLE	(Required) Title text. May be between 1–255 characters.

Example

<TAG:Title Title="Quotation">

Using Variables in Print Templates

The following example shows how to use variables in a print template.

```
<TAG:Title Title="Inventory Report">
<REM: *****variable Assignment Examples*****>
<TAG:SetVariable name="THIS IS VARIABLE" variable="VarStr">
<TAG:GetRegistry name="InstallDir" variable="VarReg">
<TAG:GetDate dayoffset="10" variable="VarDate">
<TAG:GetDate longformat="TRUE" variable="VarLongDate">
<TAG:GetTime secondoffset="-3600" variable="VarTime">
<TAG:GetTotal appletname="CS HH Product Bucket List Applet" fieldname="Quantity"
variable="VarTotal">
<TAG:GetTotal appletname="CS HH Product Bucket List Applet" fieldname="Quantity"
query="Status|Good" variable="VarGoodTotal">
<TAG:GetTotal appletname="CS HH Product Bucket List Applet" fieldname="Quantity"
query="Status|Defective" variable="VarDefectiveTotal">
<TAG:GetField appletname="CS HH Product Bucket List Applet" fieldname="Quantity"
variable="VarQuantityField">
<TAG:GetCount appletname="CS HH Product Bucket List Applet" query="Status|Good"
variable="VarGoodCount">
<TAG:GetCount appletname="CS HH Product Bucket List Applet" query="Status|Defective"
variable="VarDefectiveCount">
<REM: *****variable Assignment Examples End*****>
<REM: Inventory Print Template. This template includes 3 applets. The ENU template>
<TAG:Format Face="Helvetica" Size="16" Align="Center">
[Distributor Name
Street Address
City, Country Postal Code
Phone Number Fax Number]
```

```
<TAG:Format Face="Helvetica" Size="20" Bold="TRUE" Align="Center">
Inventory Report
<TAG:Format Face="Helvetica" Size="8" >
<TAG:Applet Name="CS HH Inv Loc Print Applet" Caption="TRUE" Wrap="TRUE">
<TAG:Applet Name="CS HH Product Bucket List Applet" Line="FALSE" Headerdivider="TRUE"
Recorddivider="FALSE" Wrap="TRUE">

<REM: *****Variable Usage Example*****>

<TAG:Divider weight="3" startat="20" endat="80">
<TAG:Cell startat="0" endat="50" name="TOTAL:" Align="RIGHT">
<TAG:Cell startat="50" endat="100" variable="VarTotal" Align="RIGHT">
<TAG:EndOfLine>
<TAG:Cell startat="0" endat="50" name="TOTAL Defective:" Align="RIGHT">
<TAG:Cell startat="50" endat="100" variable="VarDefectiveTotal" Align="RIGHT">
<TAG:EndOfLine>

<TAG:Cell startat="0" endat="50" name="TOTAL Good:" Align="RIGHT">
<TAG:Cell startat="50" endat="100" variable="VarGoodTotal" Align="RIGHT"
<TAG:EndOfLine>

<TAG:Cell startat="0" endat="50" name="Defective Count:" Align="RIGHT">
<TAG:Cell startat="50" endat="100" variable="VarDefectiveCount" Align="RIGHT">
<TAG:EndOfLine>

<TAG:Cell startat="0" endat="50" name="Good Count:" Align="RIGHT">
<TAG:Cell startat="50" endat="100" variable="VarGoodCount" Align="RIGHT">
<TAG:EndOfLine>

<TAG:Cell startat="50" endat="100" variable="VarReg">
<TAG:EndOfLine>

<TAG:Cell startat="50" endat="100" variable="VarStr">
<TAG:EndOfLine>

<TAG:Cell startat="0" endat="30" variable="VarDate">
<TAG:Cell startat="30" endat="70" variable="VarLongDate">
<TAG:Cell startat="70" endat="100" variable="VarTime">
<TAG:EndOfLine>

<REM: *****variable Usage Example End*****>

<TAG:Divider weight="2">
<TAG:Format Face="Helvetica" Size="12" Align="LEFT">
Warehouse Signature
<TAG:Divider weight="2">
<TAG:Format Face="Helvetica" Size="12" Align="RIGHT">

Rep Signature
```

F

Print Configuration Settings

This appendix includes the following topic:

[“Overview of Siebel Handheld Print Configuration Settings” on page 187](#)

Overview of Siebel Handheld Print Configuration Settings

The administrator sets up the default printer setting in the setup.ini file located in the setup directory.

There are a number of parameters to specify printing on the handheld. The parameters specify the following:

- Printer attributes (printer model, port, baud rate, and printer handshake).
- Printing attributes (portrait or landscape orientation, print density and quality, use of compression techniques, and advancing continuous-feed paper).
- Dimensions of the paper (U.S. or European standard paper sizes or custom-size paper).
- Margin settings of the pages (left, right, top, and bottom margins).

These parameters are specified in the [Printing] section of the setup.ini file located in the setup directory. The file contains default settings for all the printing parameters. Review the settings in the file to verify that these settings will work for your printing environment. If necessary, edit the settings as required. You may use any text editor to edit the file.

See [Appendix E, “Print Tagging Language,”](#) for a list of the printing parameters and valid values.

The parameters are set using the following syntax:

```
PARAMETER_NAME = VALUE
```

For example: `PrinterType = 1`

The parameters are listed below in alphabetical order by the parameter name.

MarginBottom

Use the MarginBottom parameter to specify the dimensions of the bottom margin of your page. Specify the margin in millimeters using a whole number; decimal fractions are not valid. The default is 5 millimeters.

The data specified in the Footer tag of the print template is printed in the margin specified by MarginBottom. Therefore, if the print template includes a Footer tag, you must specify a wide enough bottom margin to accommodate the footer. MarginBottom should be set to a minimum of 20 millimeters. For more information, see [“Footer” on page 175](#).

MarginLeft

Use the MarginLeft parameter to specify the width of the left margin of your page. Specify the margin in millimeters using a whole number; decimal fractions are not valid. The default is 5 millimeters.

MarginRight

Use the MarginRight parameter to specify the width of the right margin of your page. Specify the margin in millimeters using a whole number; decimal fractions are not valid. The default is 5 millimeters.

MarginTop

Use the MarginTop parameter to specify the dimensions of the top margin of your page. Specify the margin in millimeters using a whole number; decimal fractions are not valid. The default is 5 millimeters.

The data specified in the Header tag of the print template is printed in the margin specified by MarginTop. Therefore, if the print template includes a Header tag, you must specify a wide enough top margin to accommodate the footer. MarginTop should be set to a minimum of 20 millimeters. For more information, see [“Header” on page 181](#).

PaperHeight

If the paper that your printer uses is not one of the supported standard sizes, then set PaperSize to 5 (custom paper dimensions). Then, specify the height of the paper, in millimeters, using the PaperHeight parameter. You must use a whole number; decimal fractions are not valid. The default is 280 millimeters. If you specify a value of 1–4 for PaperSize, the PaperHeight parameter is ignored.

Use the PaperWidth parameter to specify the width of the paper.

PaperSize

Specify one of the standard paper sizes or specify a custom paper size. (See [Table 42](#).) If you specify custom paper size (5), you must also specify the PaperWidth and PaperHeight parameters. The default is custom paper dimensions.

See also PaperWidth and PaperHeight.

Table 42. Paper Dimensions

Value	Description
1	Letter size (8.5" x 11.5")
2	A4 (210 mm x 297 mm)
3	B5 (176 mm x 250 mm)
4	Legal size (8.5" x 14")
5 (default)	Custom paper dimensions (Specify PaperWidth and PaperHeight parameters.)

PaperWidth

If the paper that your printer is printing to is not one of the supported standard sizes, then set PaperSize to 5 (custom paper dimensions). Then, you must specify the width measurement of the paper, in millimeters, using the PaperWidth parameter. You must use a whole number; decimal fractions are not valid. The default is 5 millimeters. If you specify a value of 1–4 for PaperSize, the PaperWidth parameter is ignored.

Use the PaperHeight parameter to specify the length of the paper.

PrinterBaudrate

Use PrinterBaudrate to specify the speed of the data transmission for the printer. (See [Table 43.](#))

Table 43. Printer Baud Rate

Value	Description
0	Always use 0 for LPT or Network printer ports or for COM ports that communicate with the printer at 4800 baud
1 (default)	9600 baud
2	19200 baud
3	38400 baud
4	57600 baud
5	115200 baud

PrinterCompressed

Use PrinterCompressed to specify the data compression mode. (See [Table 44.](#)) For the printers supported in this release, always set PrinterCompressed to 1.

Table 44. Data Compression

Value	Description
0	No compression techniques used
1 (default)	Use any known compression

PrinterDensity

Use the PrinterDensity parameter to get a lighter or darker output from the printer. Start with the default setting, 2, which corresponds to the printer manufacturer’s default. As you get feedback from the field, you may need to adjust this setting.

The valid values are 0–4 where 0 is the lightest print density, 4 is the heaviest print density, and 2 is average print density.

PrinterDither

Use to specify the method by which different colors are represented. (See [Table 45.](#)) For the printers supported in this release, PrinterDither should always be set to 0.

Table 45. Print Dithering

Value	Description
0 (default)	Use color diffusion
1	Use dithering

PrinterDraftMode

Use PrinterDraftMode to specify the quality of the printing. (See [Table 46.](#)) For the printers supported in this release, PrinterDraftMode should always be set to 0.

Table 46. Print Quality

Value	Description
0 (default)	Use the highest quality printing
1	Use a lower quality printing if available

PrinterFormFeed

Use PrinterFormFeed to specify how paper advances to the next page. (See [Table 47](#).) If using sheets of paper, set PrinterFormFeed to 0.

Specify 1 or 2 for continuous-feed paper:

- Set PrinterFormFeed to 1 if you do not need to conserve paper or if you want pages of uniform length. The printer scrolls to the length specified by the PageHeight parameter and trims the page there.
- Set PrinterFormFeed to 2 to conserve paper or if it does not matter if your pages are of varying length. In this case, the printer scrolls 25 millimeters beyond the last printed line and trims the page there. The scroll distance, 25 mm, is not customizable.

For both values, 1 and 2, the page length never exceeds PageHeight.

Table 47. Printer Form Feed

Value	Description
0 (default)	Printer sends a form feed command to the printer at the end of each page. Use this setting for sheet paper.
1	Printer scrolls the page to the length specified by the PaperHeight parameter.
2	Printer scrolls the page 25 millimeters past the last printed line of the page.

PrinterHandshake

Use PrinterHandshake to define the serial port handshake. (See [Table 48](#).) The PrinterHandshake parameter applies only when the printer port is a Com1 or Com2 port. If PrinterPort is set to Com1 or Com2, then set PrinterHandshake to 1.

Table 48. Printer Handshake

Value	Description
0	Uses Xon/Xoff
1 (default)	Uses hardware control lines
2	No handshaking of serial port

PrinterOrientation

Specify whether the paper is to be oriented vertically (portrait) or horizontally (landscape). (See [Table 49.](#)) Not all printers can print in landscape orientation. Therefore, you will need to check the specifications for your printer.

Table 49. Paper Orientation

Value	Description
1 (default)	Portrait (vertical)
2	Landscape (horizontal)

PrinterPort

Specify the port to which the printer is connected with the PrinterPort parameter. (See [Table 50.](#))

If PrinterPort is an LPT port or a network path (2 or 9), then the PrinterBaudrate must be set to 0.

NOTE: The communication port on the printer must be set to be compatible with the host PDA. For IrDA, the serial communication setting must be set correctly to allow reliable printing. You should contact your printer manufacturer and Field Software for more information.

Table 50. Printer Port

Value	Description
0	Com1: serial port
1	Com2: serial port
2	LPT: parallel port
3 (default)	IR Infrared port
4	Com3: serial port
5	Com4: serial port
6	Com5: serial port
7	Com6: serial port
8	Print to file OUTPUT.PRN
9	Print to network address
10	Bluetooth BlueCard solution by Wireless Solutions
11	Socket PNC Bluetooth card support
12	Bluetooth BlueCard solution by Anycom

Table 50. Printer Port

Value	Description
13	Com7: serial port
14	Com8: serial port

PrinterType

Specify the type of printer using the PrinterType parameter. See [Table 51](#) for a list of printers supported by the Printer CE print driver used by the Siebel application.

Table 51. Supported Printers

Value	Description
0	Canon BubbleJet compatible printers
1	Citizen PD-04
2	Citizen PN60i
3	Epson ESC/P 2 compatible printers
4	Epson Stylus compatible printers
5	HP PCL compatible - includes DeskJet and LaserJet
6	Pentax PocketJet 200
7	Pentax PocketJet II
8	Seiko DPU-3445
9	Generic Epson compatible 180DPI 24-pin printers (LQ/ESC)
10	Generic Epson compatible 360DPI 24-pin printers (LQ/ESC)
11	Generic Epson compatible 203DPI 24-pin printers (LQ/ESC)
12	Extech 2"
13	Extech 3"
14	O'Neil MicroFlash
15	DymoCoStar label printers
16	Seiko LabelWriter printers
17	Extech 4"

Table 51. Supported Printers

Value	Description
18	SiPix A6 printer
102	Generic 40 column Dot Matrix Printer
108	Generic 80 column Dot Matrix Printer

Default Printing Settings

The following are the printing parameters from the setup.ini file. The values shown are the default settings.

[Printing]

```

PrinterType= 14
PrinterPort= 3
PrinterBaudrate= 1
PrinterHandshake= 1
PrinterOrientation= 1
PrinterDensity= 2
PrinterCompressed= 1
PrinterDither= 0
PrinterDraftMode= 0
PrinterFormFeed= 0
PaperSize= 5
PaperWidth= 115
PaperHeight= 280
MarginLeft= 5
MarginRight= 5
MarginTop= 5
MarginBottom= 5
    
```

Index

- A**
- accounts, managing**
 - about and Accounts screen's views 125
 - account addresses, adding 126
 - account information, adding 126
 - activities, associating with accounts 127
 - creating accounts 126
 - opportunities, adding to an accounts scenario 128
- activities**
 - about 133
 - associating with accounts 127
 - contact participants, specifying 135
 - contacts, associating with activities 134
 - creating activities 133
 - delegating activities 133
 - employee participants, specifying 135
 - general activities, adding using the Calendar view 134
- administration screens**
 - See screens
- applet classes, list of** 161
- Applet print tag** 170
- applets**
 - default behavior, overriding 24
 - form applets, designing 38
 - list applets, designing 38
 - multiple-applet views, toggling between 23
 - print applets, designing 38
 - Print buttons, configuring 39
 - printing, configuring 39
 - screen allocation 23
 - toggling between 110
 - URLs in applet fields 110
- Application Administration view** 47
- application memory, increasing** 121
- application-level menu**
 - about 108
- architecture**
 - five layers described 17
- asterisk (*)**
 - meaning in forms and applets 26
- audit trail**
 - obtaining audit trail for synchronization sessions 69
- Auto Order**
 - creating order from quote 140
 - Order Entry - Line Items view fields 165
 - Order Entry - Order business component fields 166
 - Service Products copied fields 166
- auto pop-up list**
 - about using 27
- Auto Quote**
 - about using 137
 - AutoQuote method values 163
 - creating a quote 138
 - quote items, adding 138
 - quote items, deleting 139
- automatic backup**
 - after synchronization 116
- B**
- Back button, about** 111
- backing up data**
 - about and restoring 115
 - automatic backup after synchronization 116
 - restoring data from a backup 116
 - troubleshooting 145
- backups**
 - database backup parameters, editing 90
 - external media, backing up to 90
 - restoring from 91
 - user database backups, about enabling 89
- Barcode Administration screen** 48
- barcode scanning**
 - views, enabling for 64
- barcode settings, administering**
 - barcode definition, creating 65
 - barcode definition, process of creating 65
 - barcode scanning, enabling 66
- barcode, administering**
 - about 59
 - barcode definition, creating 60
 - barcode scanning, enabling views for new barcode definitions, creating 60
- Billing field, about supporting** 142
- business component classes**
 - list of component classes 160
- business components**
 - list of supported components 159
 - synchronization conflicts, obtaining

- information 69
- business object declarations**
 - setting PDQ examples 74
- business object filters**
 - stand-alone deployments 73
- buttons**
 - about and behavior 27
- C**
- calendar**
 - about customizing 119
- Calendar view**
 - using to add general activities 134
- Cell print tag** 171
- client**
 - installation, troubleshooting backup and restore 145
 - performance troubleshooting 152
- columns, working with** 112
- Comment print tag** 173
- CompactFlash card**
 - backing up to 90
 - Siebel Handheld application, setting installation on 91
- Companion Sync**
 - architecture 15
 - caution, about synchronization failing 80
 - patches, deploying using 94
 - server, described 14
- Companion Synchronization**
 - checklist, using to troubleshoot 146
 - handheld application, using to install 103
 - log files, using for troubleshooting 149
- component level settings, configuring** 59
- configuring**
 - Siebel Handheld client 15
 - Web Client and Handheld Client, differences in configuring 18
- conflicts**
 - See synchronization, conflict handling and recover
- Contacts screen views**
 - accessing to manage contacts 123
- contacts, managing**
 - about 123
 - activities, associating with contacts 134
 - adding contacts 124
 - contact participants, specifying 135
 - Contacts screen views, accessing to manage contacts 123
 - opportunities, associating contacts with 125
 - opportunity, associating with a
 - contact 131
 - scenario 124
- customer relationships, managing**
 - about 132
 - activities, about 133
 - activities, delegating 133
 - activity, creating 133
 - contact participants, specifying 135
 - contacts, associating with activities 134
 - employee participants, specifying 135
 - general activities, adding using the Calendar view 134
 - scenario 133
- D**
- data**
 - automatic backup after synchronization 116
 - backing up, about and restoring 115
 - columns, working with 112
 - Direct Server Synchronization, using with handheld client 119
 - entering, about 112
 - exporting 114
 - Find, about using 113
 - queries, about 113
 - queries, creating/executing/refining a query 113
 - restoring data from a backup 116
 - Siebel Handheld Synchronization, using with handheld client 117
 - synchronizing data, about 117
- data filtering**
 - business object declaration examples 74
 - business object filters, general and default 73
 - developing data filters, steps 71
 - popup visibility, overriding 76
 - stand-alone deployments 73
 - visibility, designating 75
- database**
 - backup, restoring from 91
 - database backup parameters, editing 90
 - external media, backing up to 90
 - user database backups, about enabling 89
- database backups**
 - about and restoring 115
 - automatic backup after synchronization 116
 - restoring data from a backup 116
 - troubleshooting 145
- default sync filters, about deleting** 73

- quote line items 139
 - deploying**
 - CompactFlash card, setting handheld application installation on 91
 - DSS components, using Siebel Server installer 81
 - external media, installing handheld application from 92
 - multiple synchronization servers 84
 - optimizing server process management patches, deploying with Companion Sync 94
 - patches, deploying with Direct Server Sync 93
 - patches, distributing 93
 - patches, downloading 96
 - print templates, installing 91
 - server installation, server topology overview 80
 - server installation, support of Siebel Handheld Client 79
 - server logging levels, configuring 82
 - setup.ini file, editing 86
 - Siebel Handheld application, process of installing 86
 - Siebel Handheld Client, issues and validation 34
 - Siebel Handheld Direct Server Sync, server installation process 81
 - stand-alone installer, creating 92
 - synchronization performance and scalability 84
 - synchronization security 85
 - SynchURL, changing on handheld device 92
 - upgrade kits, creating to remotely deploy patch files 95
 - user database backups, enabling 89
 - diagnostics**
 - enabling SQLTrace 151
 - Direct Server Sync**
 - architecture 15
 - deploying, about 80
 - described 14
 - optimizing server process management patches, deploying using 93
 - Direct Server Sync by Means of Proxy** 15
 - Direct Server Sync deployments**
 - stand-alone deployments 73
 - Direct Server Synchronization**
 - checklist, using to troubleshoot 147
 - handheld application, using to install 105
 - handheld client, using with 119
 - log files, using for troubleshooting 148
 - network performance, troubleshooting 153
 - server performance, troubleshooting 153
 - direct synchronization server, described** 14
 - Divider print tag** 173
 - documents, defining** 37
 - downloading patches** 96
 - drilldowns, about** 33
 - drilling down, about** 111
 - DSS components**
 - using Siebel Server installer 81
 - dynamic drilldown, about** 111
 - dynamic hyperlink, about** 33
- E**
- ellipsis, and expandable fields** 110
 - employee participants, specifying** 135
 - end user error messages**
 - See troubleshooting
 - EndofLine print tag** 174
 - error messages**
 - See troubleshooting
 - errors**
 - error data, accessing 102
 - error details, obtaining from synchronization session 68
 - general synchronization errors 120
 - synchronization transaction conflicts 121
 - expenses, tracking**
 - detailed line items, adding 143
 - expense report, creating 142
 - expense report, submitting 143
 - procedures, about 142
 - exporting data** 114
 - extended insert processing**
 - about and synchronization 100
 - extended pick processing**
 - about and synchronization 97
 - enabling 98
 - external media**
 - backing up to 90
 - Siebel Handheld application, installing from 92
 - stand-alone installer, creating 92
- F**
- features, new** 11
 - Find**
 - about using 113
 - Footer print tag** 175
 - form applets, configuring**
 - about 26

- designing, about 38
 - group boxes, about 26
 - labels, about 26
 - layout sequence 26
 - Format print tag** 176
- G**
- general sync filters, about** 73
 - GetCount print tag** 177
 - GetDate print tag** 177
 - GetField print tag** 178
 - GetRegistry print tag** 179
 - GetTime print tag** 180
 - GetTotal print tag** 180
 - GotoView method, using** 24
 - group boxes**
 - about configuring 26
 - guidelines**
 - Siebel Handheld client, configuration guidelines 20
- H**
- handheld device logs**
 - list of log files 149
 - synchronization errors, logging 150
 - handheld interface**
 - See interface
 - handheld synchronization**
 - See synchronizing
 - Header print tag** 181
 - History button, about** 111
 - Home Page applet, using** 27
 - Hotel expense tax itemization**
 - about supporting 143
 - hyperlinks, about** 33
- I**
- installing**
 - client installation, backup, and restore troubleshooting 145
 - CompactFlash card, setting handheld application installation on 91
 - Companion Sync, using to install handheld application 103
 - Direct Server Sync checklist, using 147
 - Direct Server Sync, using to install handheld application 105
 - external media, installing handheld application from 92
 - patches, deploying with Companion Sync 94
 - patches, deploying with Direct Server Sync 93
 - patches, distributing 93
 - patches, downloading 96
 - reinstalling the handheld application 106
 - resynchronization problems 148
 - Siebel Handheld application, editing setup.ini file 86
 - Siebel Handheld application, process of installing 86
 - software on handheld. about 103
 - stand-alone installer, creating 92
 - synchronization, about problems caused by 146
 - SyncURL, changing on handheld device 92
 - uninstalling handheld application 106
 - upgrade kits, creating to remotely deploy patch files 95
 - upgrade, preparing from a previous release 103
 - user database backups, enabling 89
- interface**
- application-level menu 108
 - components, about and diagram 107
 - expandable fields 110
 - Minimize button 109
 - More Info view, navigation level 119
 - Queries drop-down list 109
 - screens menu, about 108
 - screens menu, navigation level 110
 - Show drop-down list, about 108
 - Show drop-down list, navigation level 110
 - Siebel toolbar, about 109
 - Siebel toolbar, customizing 109
 - status bar 109
 - tooggling between applets 110
 - URLs in applet fields 110
- inventory**
- locations, setting up 59
- L**
- labels, about configuring** 26
 - list applets, configuring**
 - about 25
 - designing, about 38
 - recommended strategy 25
 - log files**
 - Companion Sync logs, using for troubleshooting 149
 - Direct Server Sync logs, using for troubleshooting 148
 - handheld device logs, using for troubleshooting 149

M

- MarginBottom parameter** 187
- MarginLeft parameter** 188
- MarginRight parameter** 188
- MarginTop parameter** 188
- Maximize Minimize Applet button**
 - about 109
- media**
 - backing up to external media 90
 - Siebel Handheld application, installing from external media 92
 - stand-alone installer, creating 92
- memory, increasing** 121
- menu bar, about** 32
- methods**
 - AutoOrder method 165
 - AutoQuote method fields 164
 - AutoQuote method values 163
- Microsoft ActiveSync, about** 15
- Mileage expense type**
 - about supporting 143
- Minimize button, about** 109
- Mobile Web Client**
 - note, about receiving and installing upgrade kits 95
- More Info View**
 - navigation level 119
- multiple synchronization servers** 84
- Multi-Value Group applet, support of** 19

N

- naming conventions, about** 22
- network performance, about** 153
- new features** 11

O

- opportunities**
 - adding to an account 128
 - contact, associating with an opportunity 131
 - contacts, associating with an existing opportunity 125
 - creating opportunities 129
 - defined and examples 128
 - opportunity quotes, about 132
 - product, associating with an opportunity 131
 - sales methods, about 130
 - scenario 129
- orders, managing**
 - about 140
 - Auto Order, creating orders from quote 140

- manually create an order 141
- order line items, adding 141
- terms and totals, adding 142

OverridePopupVisibility

- note, if used 77

P

- Page Break print tag** 182
- PaperHeight parameter** 188
- PaperSize parameter** 188
- PaperWidth parameter** 189
- parent form applet, about** 23
- patches**
 - Companion Sync, deploying using 94
 - Direct Server Sync, deploying using 93
 - distributing 93
 - downloading to the handheld device 96
 - upgrade kits, creating to remotely deploy patch files 95
- PDQs**
 - and Queries drop-down list 109
- performance**
 - application memory, increasing 121
 - client performance, about 152
 - improving by identifying user activities 20
 - improving performance, about 121
 - network performance, about 153
 - server performance, about 153
 - SQLTrace and synchronization 151
- pick applets**
 - business object declaration examples 74
 - popup visibility, overriding 76
 - visibility, designating 75
- Picture print tag** 182
- pop-up lists**
 - about using auto pop-up lists 27
- popup visibility, overriding** 76
- predefined queries**
 - and Queries drop-down list 109
- preferences**
 - setting user preferences 115
- print applets**
 - about designing 38
- Print buttons, configuring** 39
- print tagging language**
 - See print templates
- print templates**
 - Applet print tag 170
 - Cell print tag 171
 - Comment print tag 173
 - creating print templates 40
 - Divider print tag 173
 - EndofLine print tag 174

- Footer print tag 175
- Format print tag 176
- GetCount print tag 177
- GetDate print tag 177
- GetField print tag 178
- GetRegistry print tag 179
- GetTime print tag 180
- GetTotal print tag 180
- Header print tag 181
- Page Break print tag 182
- Picture print tag 182
- print template file example 185
- print template file, creating overview 169
- SetVariable print tag 184
- Static Text print tag 184
- Title print tag 184
- variables, example using in template 185
- views, associated with 24
- print templates, installing** 91
- PrinterBaudrate parameter** 189
- PrinterCompressed parameter** 190
- PrinterDensity parameter** 190
- PrinterDither parameter** 190
- PrinterDraftMode parameter** 190
- PrinterFormFeed parameter** 191
- PrinterHandshake parameter** 191
- PrinterOrientation parameter** 192
- PrinterPort parameter** 192
- PrinterType parameter** 193
- printing**
 - quotes 140
- printing with handheld application** 114
- printing, configuration settings**
 - default printing settings, list of 194
 - MarginBottom parameter 187
 - MarginLeft parameter 188
 - MarginRight parameter 188
 - MarginTop parameter 188
 - PaperHeight parameter 188
 - PaperSize parameter 188
 - PaperWidth parameter 189
 - parameters and syntax 187
 - PrinterBaudrate parameter 189
 - PrinterCompressed parameter 190
 - PrinterDensity parameter 190
 - PrinterDither parameter 190
 - PrinterDraftMode parameter 190
 - PrinterFormFeed parameter 191
 - PrinterHandshake parameter 191
 - PrinterOrientation parameter 192
 - PrinterPort parameter 192
 - PrinterType parameter 193
- printing, configuring from handheld application**
 - about 37
 - applet, configuring for printing 39
 - documents, defining 37
 - form applets, designing 38
 - list applets, designing 38
 - print applets, designing 38
 - Print buttons, configuring 39
 - print templates, creating 40
- products**
 - associating with an opportunity 131
- projects**
 - naming conventions, and 22
- Q**
- queries**
 - about using 113
 - creating/executing/refining a query 113
- Queries drop down list**
 - about 109
- quotes, developing**
 - about 136
 - Auto Order, creating from quote 140
 - Auto Quote, about using 137
 - Auto Quote, creating a quote 138
 - creating quotes 136
 - developing quotes scenario 136
 - opportunity quotes, about 132
 - printing quotes 140
 - quote item, adding 138
 - quote item, deleting 139
- R**
- record navigation buttons** 111
- records, navigating a list of**
 - about 111
 - Back button 111
 - record navigation buttons 111
- reinstalling the handheld application** 106
- removing**
 - business component filter setting 51
 - business object filter section 52
- reports**
 - associating views with 24
 - expense report, creating 142
 - expense report, submitting 143
- repository**
 - compiling 34
- responsibilities**
 - assigning 49
- restoring data**
 - from a backup 116
 - Siebel Handheld Client, using 115
 - troubleshooting 145

restoring from a backup 91

S

sales methods, about 130

screens

administrative screens, about 47
 designing screens for Siebel Handheld,
 about 23
 screen allocation 23
 views, list of 155

screens menu

about 108
 navigation level 110

scripting

Siebel Handheld Client, issues and
 validation 34

server installation

DSS components, using Siebel Server
 installer 81
 hardware and network configuration
 recommended 80
 optimizing server process management 84
 server logging levels, configuring 82
 server topology overview 80
 Siebel Handheld Client, support of 79
 Siebel Handheld Direct Server Sync, server
 installation process 81

server logging levels, configuring 82

server performance

troubleshooting 153

servers

multiple synchronization servers 84

ServiceCE Generic

about 32

Session Administration screen 47

SetVariable print tag 184

Shipping field, about supporting 142

Show drop-down list

about 108
 navigation level 110

Siebel eConsumer Handheld

business component classes, list of 160

Siebel Handheld application

CompactFlash card, setting installation
 on 91
 external media, installing from 92
 patches, deploying with Companion
 Sync 94
 patches, deploying with Direct Server
 Sync 93
 patches, distributing 93
 patches, downloading 96
 process of installing 86

setup.ini file, editing 86
 stand-alone installer, creating 92
 SyncURL, changing on handheld device 92
 upgrade kits, creating to remotely deploy
 patch files 95
 user database backups, enabling 89

Siebel Handheld Client

application memory, increasing 121
 auto-pop-up list, using 27
 backing up and restoring data, using 115
 configuration guidelines 20
 Direct Server Synchronization, using with
 handheld client 119
 form applets, about configuring 26
 general synchronization errors 120
 hardware and network configuration
 recommended 80
 Home page applet, about 27
 hyperlinks, about 33
 improving performance, about 121
 list applets, configuring 25
 menu bar, about 32
 Multi-Value Group applet, support of 19
 printing, configuring 37
 process of configuring 17
 repository, compiling 34
 scripting, issues and validation 34
 server installation, support of Siebel Handheld
 Client 79
 server topology overview 80
 Siebel Web Client, differences in
 configuring 18
 status bar, about 33
 synchronization transaction conflicts 121
 testing the handheld application 46
 toolbars, about 32
 unsupported functions 19
 user functionality, defining 20
 user interface elements, about
 configuring 25

Siebel Handheld Direct Server Sync

DSS components, using installer 81
 optimizing server process management 84
 process of server installation 81
 server logging levels, configuring 82

Siebel Handheld projects

about creating and naming conventions 22

Siebel Handheld Synchronization

application memory, increasing 121
 Direct Server Synchronization, using with
 handheld client 119
 general synchronization errors 120
 handheld client, using 117
 improving performance, about 121

- synchronization transaction conflicts 121
 - Siebel toolbar**
 - about 109
 - customizing 109
 - Siebel Web Client**
 - Multi-Value Group applet, support of 19
 - Siebel Handheld client, differences in configuring 18
 - unsupported functions 19
 - software**
 - about installing on handheld 103
 - SQLTrace, enabling** 151
 - .SRF file**
 - compiling repository file 34
 - SSL (Secure Sockets Layer)**
 - synchronization security 85
 - stand-alone deployments, about** 73
 - stand-alone installer, creating** 92
 - Static Text print tag** 184
 - status bar**
 - application window, appears at bottom of 109
 - toolbar, located above 33
 - submitting**
 - expense report 143
 - synchronization sessions**
 - error details, obtaining from 68
 - monitoring 68
 - monitoring, about 67
 - synchronization conflicts, obtaining information 69
 - synchronization sessions, obtaining an audit trail 69
 - synchronization transaction errors, acting on 70
 - synchronization, conflict handling and recovery**
 - about 97
 - error data, accessing 102
 - extended insert pick processing, about 100
 - extended pick processing, about 97
 - extended pick processing, enabling 98
 - synchronizing**
 - application memory, increasing 121
 - automatic backup after synchronization 116
 - Companion Sync 15
 - data, about 117
 - Direct Server Sync 15
 - Direct Server Sync by Means of Proxy 15
 - Direct Server Synchronization, using with handheld client 119
 - filters, general and default business object
 - filters 73
 - general synchronization errors 120
 - handheld synchronization errors, logging 150
 - improving performance, about 121
 - methods and architecture 14
 - multiple synchronization servers 84
 - overview 14
 - performance and scalability, about 84
 - resynchronization problems, troubleshooting 148
 - servers, types of 14
 - Siebel Handheld Synchronization, using with handheld client 117
 - synchronization security 85
 - transaction conflicts 121
 - troubleshooting, about problems caused by 146
 - SyncURI**
 - changing on handheld device 92
- ## T
- templates**
 - install templates, installing 91
 - print templates, creating 40
 - print templates, views associated with 24
 - terms, adding to order line items** 142
 - testing the handheld application** 46
 - timeout parameter**
 - changing on Windows 2000 151
 - Title print tag** 184
 - toggling between applets** 110
 - toolbars**
 - about 109
 - configuring 33
 - customizing 109
 - toolbar functions 32
 - totals, adding to order line items** 142
 - troubleshooting**
 - client installation, backup, and restore 145
 - client performance, about 152
 - Companion Sync checklist, using 146
 - Companion Sync log files 149
 - Direct Server Sync checklist, using 147
 - Direct Server Sync log files 148
 - general synchronization errors 120
 - handheld device logs 149
 - network performance, about 153
 - resynchronization problems 148
 - server performance, about 153
 - SQLTrace, enabling 151
 - synchronization transaction conflicts 121
 - synchronization, about problems caused

- by 146
- timeout parameter, changing on Windows 2000 151

U

ui

- See user interface elements, configuring

uninstalling the handheld application 106

upgrade kits

- creating to remotely deploy patch files 95

upgrading

- handheld application 106
- preparing to upgrade 103

URLs

- in applet fields, 110

User Administration screen 47

user database backups

- backup, restoring from 91
- database backup parameters, editing 90
- enabling, about 89
- external media, backing up to 90

user functionality, defining

- about 20

user interface elements, configuring

- about 25
- auto pop-up lists, about using 27
- buttons, about and behavior 27
- form applets, about configuring 26
- Home Page applet, about 27
- hyperlinks, about 33
- list applets, about configuring 25
- menu bar, about 32
- status bar, about using 33
- toolbars functions 32
- toolbars, about configuring 33

user preferences

- about customizing 115

user properties

- list of 163

users, setting up

- barcode definition, creating 65
- barcode definition, process of creating 65
- barcode scanning, enabling the SHCE Service FS Activity Parts Movements views 66
- barcode scanning, enabling views for 64
- barcode settings, administering 59
- business component filter setting, adding 50
- business object filter section, adding 52
- business object filter section, removing 52

- component level settings, configuring 59
- error details, obtaining from synchronization sessions 68

- new barcode definitions, creating 60

- process tasks 48

- responsibilities, assigning 49

- synchronization conflicts, obtaining information 69

- synchronization sessions, about monitoring 67

- synchronization sessions, monitoring 68

- synchronization sessions, obtaining an audit trail 69

- synchronization transaction errors, acting on 70

- user level settings, removing 51

- views, administering 49

- views, methods for specifying 50

V

views

- default behavior, overriding 24

- drill-down only 23

- print templates or reports, associated with 24

- Siebel Handheld, about designing views for 23

views, administering

- business component filter setting, adding 50

- business object filter section, adding 52

- business object filter section, removing 52

- component level settings, configuring 59

- tasks associated with 49

- user level settings, removing 51

- views, methods for specifying 50

visibility

- designating in default Business Object declarations 75

- OverridePopupVisibility, if used 77

- popup visibility, overriding 76

W

Web server timeout errors

- changing timeout parameter on Windows 2000 151

Windows

- changing timeout parameter on Windows 2000 151

