



BEA AquaLogic® Enterprise Repository

Administration Guide

Version 3.0 RP1
Revised: February, 2008


Table of Contents

- **AquaLogic Enterprise Repository Administration**
- **Users**
 - **Creating a New User**
 - **Viewing User Information**
 - **User Search**
 - **Cloning a User**
 - **Editing User Information**
 - **User Status**
- **Sessions**
 - **Using Sessions**
- **Roles**
 - **User Role Descriptions**
 - **Creating a New Role**
 - **Editing a Role**
 - **Deleting a Role**
- **Departments**
 - **Creating a New Department**
 - **Editing Department Information**
- **Projects**
 - **Enable Project Categorizations**
 - **Using Project Categorizations**
- **Basic Access Settings**
 - **Granting Permissions to a Role**
 - **Editing Permissions**
 - **Verifying User Permissions**
- **System Settings**
 - **Access System Settings**
 - **Search for System Settings**
 - **Enable System Settings Properties**
 - **Move Settings to Database**
 - **Functional Settings**
 - **General User Interface**

- [Search](#)
 - [Projects and Navigator](#)
 - [Notifications](#)
 - [Use - Download](#)
 - [Custom Links](#)
 - [Reports](#)
 - [Miscellaneous](#)
- **Server Settings**
 - [General](#)
 - [Server Resources](#)
 - [Email](#)
 - [Upload Area](#)
 - [Caching](#)
- **Enterprise Authentication Settings**
 - [General](#)
 - [Authentication Token](#)
 - [Password Settings](#)
 - [Plugin Login Settings](#)
 - [Container Login Settings](#)
 - [Cookie Login Settings](#)
- **External Integration Settings**
 - [UDDI](#)
 - [Eventing](#)
- **Import/Export and Introspection**
 - [Import / Export](#)
 - [WSDL and XSD](#)
- **BPEL**
 - [Import from BPEL](#)
- **Email Templates**
 - [Editing Email Templates](#)

AquaLogic Enterprise Repository Administration

Within the AquaLogic Enterprise Repository **Admin** section, administrators can configure the application, add users, and assign roles and access settings for users. The **Admin** section also provides the means to configure sessions and add departments. Typically, **Admin** tasks are restricted to system or access administrators.



The **Admin** section encompasses the following administrative functions:

- **Users**
 - Create, edit, and search for users.
- **Sessions**
 - Monitor which users are logged into the system. Using this function an administrator can also log a user out of the system.
- **Roles**
 - Allows the administrator to add, edit, modify, and assign roles to specific users. Examples: *general*, *user*, *administrative user*.
- **Departments**

- Create, list, or edit departments. Departments must be created before users can be assigned to them.
- **Basic Settings**
 - Default permission settings that determine the role-based access to the various features of AquaLogic Enterprise Repository.
- **Custom Settings**
 - Customizable role-based permission settings.
- **System Settings**
 - System configuration for general, authentication, LDAP (if enabled) and access settings, as well as enabling additional system properties.
- **Email Templates**
 - Edit automatic email templates used for various notifications of activity in AquaLogic Enterprise Repository.
- **SFID Manager** (Available only in the Advanced Edition of ALER)
 - Provides the ability to determine asset usage independent of the manual asset **Use - Download** process within ALER.

Users


Creating a New User

This procedure is performed on the BEA AquaLogic Enterprise Repository **Admin** screen.

1. In the left panel, click **Users**.
2. Click **Create New** in the **Users** section.

The **Create New User** pop-up opens.

3. Enter the appropriate information in each of the text boxes in the **Overview** section.



Overview

Username*:

First Name:

Middle Name:

Last Name*:

Email*:

Phone:


Status: **Active** ▼

Password*:


Must change password on next login

Password never expires

4. Select **Active** in the **Status** drop-down.
5. In the **Roles** section, assign roles to the new user by using the **>>** and **<<** buttons to move items from the **Available Roles** column to the **Selected Roles** column. (The **User** role is the default role for all new users.)



6. In the **Departments** section, assign the new user to departments by using the >> and << buttons to move items from the **Available Departments** column to the **Selected Departments** column.




7. When finished, click **Save**.

Viewing User Information

This procedure is performed on the BEA AquaLogic Enterprise Repository **Admin** screen.

1. In the **Users** section, use **Search** or **List All** to locate the user(s) to be viewed.


The list of users opens in the main pane.




2. Select a user from the list.

The user's information is displayed in the lower pane.

3. Click  to expand the **User** detail to fill the main pane.

4. Click  to switch to the tabbed view of the **User** detail.



5. Click  to switch back to the standard view of the **User** detail.

6. Click  to scroll through the list of users.

User Search

This procedure is performed on the BEA AquaLogic Enterprise Repository **Admin** screen.

1. Enter appropriate text in the **Name** text box.
2. Use the Department, Role, and **Status** drop-downs as appropriate to narrow the search.
3. Click the **Search** button.

Search results appear in the list in the upper frame of the main pane.

Cloning a User

Overview

Cloning a user provides an easy way for administrators to quickly duplicate user accounts.

This procedure is performed on the BEA AquaLogic Enterprise Repository **Admin** screen.

1. In the **Users** section, use **Search** or **List All** to locate the user to be cloned.
2. Click the **Clone** button in the user detail.

The **Clone User** pop-up opens (same form as the **Create New User** pop-up). The **Overview** section will be blank, but information in the **Roles** and **Departments** sections duplicates that of the cloned user.

3. Enter the appropriate information in each of the text boxes in the **Overview** section.
4. If necessary, edit the information in the in the **Roles** and **Departments** sections by using the **>>** and **<<** buttons to move items between the **Available** and **Selected** columns.
5. When finished, click **Save**.

Editing user Information

This procedure is performed on the BEA AquaLogic Enterprise Repository **Admin** screen.

1. In the **Users** section, use **Search** or **List All** to locate the user(s) to be edited.

The list of users opens in the main pane.

2. Select a user from the list.

The user's information is displayed in the lower pane.

3. Click the **Edit** button in the user detail.

The **Edit User** pop-up opens (same form as the **Create New User** and **Clone User** pop-ups).

4. Make changes as necessary in the **Overview**, **Roles**, and **Departments** sections.
5. When finished, click **Save**.

User Status

Overview

BEA AquaLogic Enterprise Repository users are assigned to one of four states:

- **Active**
 - User can log in to BEA AquaLogic Enterprise Repository. Active users are counted as valid users regardless of the licensing model in effect.
- **Inactive**
 - User is unable to log in to BEA AquaLogic Enterprise Repository.
 - Example: **Inactive** status is assigned to terminated employees.
- **Locked Out**
 - Users who have exceeded the maximum number of failed login attempts (as configured in **System Settings**). The user will remain locked out until an access administrator changes the user's account status to **Active**.
- **Unapproved**
 - Valid when using LDAP or SSO.
 - User account is newly created, but requires a user with access administrator privileges to update the user's account (roles, departments, etc.)
 - *Under LDAP*
 - User account is created on initial BEA AquaLogic Enterprise Repository login, status: **Unapproved**.
 - Options:
 - If the **Unapproved User Login** property is set to **True**:
 - User can login, with permissions as determined by the assigned default role. (Behavior is consistent with **Active** user.)
 - If the **Unapproved User Login** property is set to **False**:
 - User can login, but will be unable to see any assets or perform any BEA AquaLogic Enterprise Repository tasks until the access administrator changes the user's status to **Active**, and assigns to a **Role** and optionally to **Departments**.

(Behavior is consistent with **Inactive** user.)

- *Under SSO*
 - User accounts under SSO are best managed via the default BEA AquaLogic Enterprise Repository **Roles** and their relevant permissions. User access to assets and BEA AquaLogic Enterprise Repository features can be controlled by limiting the permissions granted to the default role assigned to the user at login. These roles must be assigned via BEA AquaLogic Enterprise Repository if role synchronization through the User Directory is not in use.

A user's access may be reset by removing all of his/her permissions. Upon subsequent login, the user will be assigned only the permissions assigned to the default role.

Changing User Status

This procedure begins on the BEA AquaLogic Enterprise Repository **Admin** screen.

1. Use **User Search** or other means to locate the user whose status is to be changed.
2. Click the **Edit** button in the **User Detail**.

The **Edit User** pop-up opens.

3. Use the **Status** drop-down in the **Overview** section of the **Edit User** pop-up to select the new user status.

The screenshot shows the 'Overview' section of the 'Edit User' pop-up. It includes the following fields and options:

- Username*: smth
- First Name: John
- Middle Name: (empty)
- Last Name*: Smth
- Email*: smth@email.com
- Phone: (empty)
- Status: Active (dropdown menu is open showing: Active, Inactive, Locked Out, Unapproved)
- Password*: (empty) password on next login
- Password never expires

4. Click the **Save** button to save changes and close the **Edit User** pop-up.

Sessions

Overview

Sessions allows the administrator to see which users are logged in to AquaLogic Enterprise Repository and, if necessary, shut down a user session.


Using Sessions

This procedure is performed on the AquaLogic Enterprise Repository **Admin** screen.

(Requires the **Delete** permission. See [Access Settings](#).)

1. In the left panel, click **Sessions**.

A list of sessions opens in the main pane.



Deleting a Single Session

1. Select the session to be deleted from the list in the main pane.

The session's detail opens in the bottom frame.

2. Click the **Delete** button in the session detail.

A confirmation pop-up opens.

3. Click **OK**.

The session is deleted.

Deleting Multiple Sessions

1. In the list of session in the main pane, place a checkmark next to each session to be deleted.
(Place a checkmark in the checkbox at the top of the column to select all listed sessions.)

2. Click the **Delete** button above the list.

A confirmation pop-up opens.

3. Click **OK**.

The sessions are deleted.

Roles

Clicking the **Roles** link in the AquaLogic Enterprise Repository menu bar allows administrators to set up roles for an organization's various functions. AquaLogic Enterprise Repository access settings are established for each role, and each user is assigned a specific role based on his/her function within the organization.

Users assigned the **admin** role have unlimited access to all AquaLogic Enterprise Repository (ALER) functions. By default, in either a new installation or a migration from a previous version, the user account identified as **admin** is assigned the **admin** role in order to facilitate initial installation and configuration. It is highly recommended that you limit the assignment of **admin** privileges to the original **AquaLogic Enterprise Repository** user account and no more than one additional account. The various default roles established in AquaLogic Enterprise Repository offer a variety of privileges to satisfy the functions and responsibilities for any and all AquaLogic Enterprise Repository users. These roles may be customized to suit the particular needs of your organization.

User Role Descriptions

The various default roles shipped with AquaLogic Enterprise Repository are listed below. Users with access to the **Admin** tab can change role names to suit organizational needs. The permissions granted to these roles can be changed in the **Access Settings** section.

- **User**
 - Anyone with an AquaLogic Enterprise Repository user name and password is considered to be a user. This role can be assigned as the default role for any new users at the time the user is created. All AquaLogic Enterprise Repository users can:
 - View news about the company's reuse initiatives
 - Locate, evaluate, and use/download assets
 - View projects
 - Generate reports
 - Submit assets to the registrar
- **Access Administrator**
 - The access administrator creates all AquaLogic Enterprise Repository users, and assigns permissions to them. The access administrator must be familiar with the functions of the Admin Tab. Typically, access administrators can:
 - Create, view, and edit users and permissions
 - Generate reports
- **Advanced Submitter**
 - The advanced submitter role is typically assigned to asset builders and harvesters. Asset builders focus on building the asset content base. They respond to organization-wide asset needs as well as individual project needs. Harvesters study post-implementation projects for asset reuse potential. Typically, advanced submitters can:
 - Locate, evaluate, and use/download assets


- View projects
 - Generate reports
 - Submit assets to the registrar
 - Edit asset metadata prior to asset registration
- **Registrar**
 - The registrar is responsible for the acceptance or rejection of any asset. There may be more than one person functioning as a repository registrar, depending on the functions addressed. Typically, registrars can:
 - Locate, evaluate, and use/download assets
 - View projects
 - Generate reports
 - Submit assets to the registrar
 - Edit asset metadata prior to asset registration
 - Accept assets for the registration process
 - Approve tabs
 - Register assets
 - Edit access settings
- **Registrar Administrator**
 - The registrar administrator is able to establish Types within AquaLogic Enterprise Repository, using the **Type Manager**. Typically, registrar administrators can:
 - Locate, evaluate, and use/download assets
 - View projects
 - Generate reports
 - Submit assets to the registrar
 - Edit asset metadata prior to asset registration
 - Accept assets for the registration process
 - Approve tabs
 - Register assets
 - Edit access settings
 - Edit Artifact Stores and Types
- **Project Administrator**
 - AquaLogic Enterprise Repository tracks asset use at the project level in order to maintain a history for maintenance purposes. Project administrators create projects and assign users to projects using the Projects Tab, visible to users with appropriate permissions. Project administrators can also close projects, indicate which assets were deployed, and review, validate, and optionally override the predicted and consumer-reported value of assets used in a project through the project-reported asset value user interface. Typically, project administrators can:
 - Create, edit, and view projects
 - Generate reports
- **System Administrator**
 - The system administrator configures AquaLogic Enterprise Repository for use, including, possibly, installation as well as the post-installation configurations. The system administrator typically can:
 - Enable and edit system settings
 - Generate reports

(The system administrator role should not be assigned to general users.)

Creating a New Role

This procedure is performed on the AquaLogic Enterprise Repository **Admin** screen.

1. In the left panel, click **Roles**.
2. Click **Create New**.



The screenshot shows a web interface titled "Roles". At the top left, there is a double arrow icon. Below the title, there are two links: "Create New" and "List All". A "Search" section follows, with a blue header. Under "Search", there is a "Name" label and an empty text input field. Below that is a "Default" label and a dropdown menu currently showing "Unspecified". At the bottom of the search section, there is a "Search" button.

3. In the **Create New Role** dialog box, enter a role name and description in the text fields in the **Overview** section.

Create New Role

Overview

Name*:

Description:

(Max 500 Characters)

Automatically assign to new users?

Users

*Denotes required field

4. If necessary, check the **Automatically assign to new users?** box.
5. Click the **Edit Users** in the **Users** section.

The **Add New Users** pop-up opens.

Search / Filter Users and Access Settings

Find Users

Name

Department

Role

Status

Available Users

Selected Users

userTest1.

6. Use **Search** or click **List All** to locate users.

- Use the >> and << buttons to move users between the **Available Users** and **Selected Users** columns.
- When finished, click **Save**.

To add access settings to the role, see [Granting Permissions to a Role](#)

Editing a Role

This procedure is performed on the AquaLogic Enterprise Repository **Admin** screen.

- In the left panel, click **Roles**.

A list of roles is displayed in the main pane.

The screenshot shows a web interface for managing roles. At the top left is a 'Delete' button. The main area contains a table with 9 results. The table has columns for 'Role Name', 'Default', and 'Description'. Below the table, the details for the 'accessAdministrator' role are shown, including an 'Overview' section with the role's name and description, and a 'Users' section listing 'Admin, Repository' and 'priv, all'. There are 'Edit' and 'Delete' buttons for the selected role.

<input type="checkbox"/>	Role Name	Default	Description
<input checked="" type="checkbox"/>	accessAdministrator		Access Administrator
<input type="checkbox"/>	advancedSubmitter		Advanced Submitter
<input type="checkbox"/>	businessAnalyst		Business Analyst
<input type="checkbox"/>	projectAdministrator		Project Administrator
<input type="checkbox"/>	projectArchitect		Project Architect
<input type="checkbox"/>	registrar		Registrar
<input type="checkbox"/>	registrarAdministrator		Registrar Administrator
<input type="checkbox"/>	systemAdministrator		System Administrator
<input type="checkbox"/>	user	yes	Normal User

Role: accessAdministrator

Overview
Name: accessAdministrator
Description: Access Administrator

Users
Admin, Repository
priv, all

- Use **Search** or browse the list to locate the Role to be edited.
- Click on the role to display its information in the lower pane.
- Click the **Edit** button in the role detail (bottom frame).

The **Edit Role** pop-up opens.

Edit Role: user

Overview

Name*: user

Description: Normal User

(Max 500 Characters)

Automatically assign to new users?

Users

Admin, Repository
priv, all
ProjectTestUser1, ProjectTestUser1 P.
ProjectTestUser2, ProjectTestUser2 P.
userTest1.
userTest2.
UserTestUser1, UserTestUser1 U.

Edit Users

*Denotes required field

Save **Cancel**

5. If necessary, click **Edit Users** in the **Users** section to edit the users assigned to this role. (Same as **Step 5** in **Creating a New Role**.)
6. When finished, click **Save**.

Deleting a Role

This procedure is performed on the AquaLogic Enterprise Repository **Admin** screen.

(Requires the **Delete** permission. See [Access Settings](#).)

1. In the left panel, click **Roles**.
2. Use **Search** or browse the list in the main pane to locate the role to be deleted.
3. Option 1:
 - o In the list in the upper frame, place a check in the box next to each role to be deleted.
 - o Click **Delete**.
4. Option 2:
 - o Select the role in the list in the upper pane to display its information in the lower pane.
 - o Click the **Delete** button in the role detail (lower frame).
5. Click **OK** in the delete confirmation.

- **Note:** Deleted roles will no longer appear in **Access Settings**.


Departments

Departments should be set up before **Users** and **Projects**.

Creating a New Department

This procedure is performed on the **Admin** screen.

1. In the left panel, click **Departments**.
2. Click **Create New**.
3. In the **Create New Department** dialog box, enter the appropriate information in each of the text boxes.



Edit Department: Development

Name*:

Description:

(Max 4000 Characters)

*Denotes required field

4. When finished, click **Save**.

Editing Department Information

This procedure is performed on the **Admin** screen.

1. In the left panel, click **Departments**.
2. Click **List All**, or search for a particular department.
3. Select the department to be edited from the list in the right panel.

The department's detail is displayed.

4. Click **Edit** in the department detail.
5. In the **Edit Department** dialog box, update the text boxes as required.
6. When finished, click **Save**.

Projects

Overview

Projects are the primary means of gathering metrics in ALER. ALER tracks assets produced by projects, as well as assets consumed by projects. ALER users are assigned to projects, and when a user submits a new asset, they are prompted for the producing project. Likewise, when a user wants to reuse an asset, they are prompted for the project on which the asset will be reused. This level of tracking allows ALER to generate reports on the reuse savings per project. It also allows ALER to report on the savings generated by asset production teams. Projects are also hierarchical, which allows organizations to, for example, establish a program that may spawn many projects.

Projects are also a channel for governance practices. ALER Compliance Templates (usually taking the form of Architecture Blueprints or Project Profiles) can be applied to projects. The compliance templates indicate assets that should be used on the project to fulfill the project's functional and non-functional requirements. This allows business analysts, architects, project managers, and other roles/functions involved in the early phases of the software development life cycle to communicate or prescribe assets that should be leveraged by development teams.

The ALER **Projects** page provides access to tools for creating and managing projects.

The screenshot displays the ALER Projects page. On the left is a search sidebar with fields for Name, Department (set to 'All Departments'), and Status (set to 'All States'), along with a 'Search' button. The main area shows a table with two results:

Project	Department	Status
example Smith, Joe - MyProject	Development	Open
Registry	Development	Open

Below the table, the 'Registry' project is selected, showing a detailed view with tabs for Overview, Compliance Templates, Consumed Assets, Users, and Related Projects. The 'Overview' tab is active, displaying the following information:

- Registry**
- Description:** The Registry project
- Department:** Development
- Start Date:** 2007-06-19
- Estimated Hours:** 42
- Status:** Open

Viewing Project Details


Project information is displayed the same as asset information, using a series of tabs:

Overview

Includes a project **Description**, and indicates the assigned **Department**, **Start Date**, **Estimated Hours**, and project **Status**.


Compliance Templates

Displays the **Compliance Template(s)** assigned to the project.



Consumed Assets

Lists any assets used in (or under consideration for use in) the project.



Click the **Zoom** icon next to any listed asset to display its **Reported Asset Value**.

- Project members can view the **Asset Usage Detail**.
- Project leaders can view/edit the **Reported Asset Value**.

Reported Asset Value of Asset: Sample Application - Commercial Card Authorization System to the Project: example Smith, Joe - MyProject

Project Leads are responsible for accurate reporting of the hours saved by reusing assets on their projects. The Project Lead may select the Predicted Value or Consumer Value, or enter a new value to determine the **Reported Asset Value to the Project**. Use the radio buttons to select the appropriate value.

Predicted Value - This value is provided by the asset Producer. It represents the total hours the Producer expects the Consumer to save.
Consumer Value - This value is provided by the Consumer. It represents the actual time savings declared by the Consumer.
Project Lead Value - This value is provided by the Project Lead. The Project Lead can enter a different value to override all other values.

Rejected instances of use will not be included in Breakdown by Usage Type and Total Asset Value.

Instances of Use	Predicted Value		Consumer Value		Project Lead Value		Reported Asset Value to Project		
	User	Date	Status	Hrs Saved	Hrs Saved	Usage Type?	Valuable?	Hrs Saved	Usage Type
* Smith, Joe	2007-06-19	IN PROCESS	0.0	-	-	*	0	Unspecified	Unspecified 0.0 predicted

* - Results have not been reviewed by project lead

- **Reported Asset Value** represents the hours saved by reusing assets on their projects. This value is derived from either the Predicted Value, Consumer Value, or a completely new value determined by the project leader. Only the project leader can set this value.

Produced Assets

Lists any assets produced by the project.


Project: **projectTest1**

Overview | Compliance Templates | Consumed Assets | **Produced Assets** | Users | Related Projects

Asset
Sample Service (2)

Users

Lists all users associated with the project, as well as each user's role on the project (leader/members). Project leaders have the ability to assign a Reported Asset Value value to assets consumed by the project.



Related Projects

When enabled, lists any related projects, and defines the relationships in parent/child terms.

Creating a Project

This procedure is performed on the **Projects** page.

1. In the left panel, click **Create New**.

The Create New Project pop-up opens.

Create New Project

Overview

Name*:

Description:
(Max 4000 Characters)

Estimated Development Hours:

Start Date*: 2007-06-24

Department*: Select Department

Status: Open

Automatically assign to new users?

Users

Project Leaders* Project Members


Related Projects

Parent Projects Child Projects

*Denotes required field


2. Enter the appropriate information in the **Name**, **Description**, and **Estimated Development Hours** text boxes.
3. Click the ... button to open the calendar to select a **Start Date**.
4. Select a department from the **Department** drop-down.
5. Select the appropriate status in the **Status** drop-down.
6. If necessary, select **Automatically Assign New Users**.
7. Click **Edit** in the Users section.

The Add/Remove Users pop-up opens.



8. Use **Search** or **List All Users** to display a list of users in the Search Results section.
 - Use the **Department** drop-down to filter search results.
9. Use the >> and << icons to move users between the Search Results, Project Leaders, and Selected Users sections.
10. Click **OK**.

The assigned **Project Leaders** and **Project Members** appear in the Users section of the Create New Project pop-up.



11. Click **Save**

The Create New Project pop-up closes, and the new project detail appears on the Projects page.



Editing a Project


This procedure is performed on the **Projects** page.

1. Use **Search** or other means to locate the project to be edited.
2. Click **Edit** in the project detail.
3. Edit the project information as necessary. (See [Create a Project.](#))

Reassigning Users / Usage

This procedure is performed on the **Projects** page.

1. Select the **Users** tab.




2. Click **Reassign Users/Usage**.

The Reassign pop-up opens.

3. Use the radio buttons to select the appropriate action.


4. Click **Choose a New Project**.

The Search for a Project pop-up opens.



5. Use **Search** or **List All Projects** to display a list of projects.
6. Select the project to which the users and/or usages are to be reassigned.
7. Click **Ok**.
8. Click **Next**.

The **Select users you wish to reassign** pop-up opens.



9. Use the >> and << icons to reassign users as Project Leaders and/or Project Members.
10. Click **Next**.
A confirmation message appears.
11. Click **Done**.

Locating a Project

This procedure is performed on the **Projects** page.

1. Enter a keyword or search term in the **Name** text box.
2. Use the **Department** and **Status** drop-downs as necessary to filter the search.
3. If enabled, you can also filter by **Categorizations**.
4. Click **Search**.

Search results are listed in the main pane.

Project Categorizations


Overview

The **Project Categorizations** feature provides the means to assign projects to various categories established in BEA AquaLogic Enterprise Repository.


Activating Project Categorizations

This procedure is performed on the BEA AquaLogic Enterprise Repository **Admin** screen.


1. Click **System Settings**.



The **System Settings** section opens in the main pane.




2. Enter `cmee.projecttool.categorizations` in the **Enable New Property** text box.



3. Click **Enable**.

Advanced Project Option - Categorization appears in the **Projects and Navigator** grouping in the **Functional Settings** section.



4. Make sure **True** is selected.
5. Click **Save**.


The **Project Categorizations** feature is now enabled. See [Using Project Categorizations](#) for more information.

Using Project Categorizations


Configuring Project Categorizations

This procedure is performed in the **Asset Editor**.

1. Open the **Actions** menu.
2. Select **Configure Categorizations**.




3. Select the categorization to be assigned to projects.



4. Click the **Edit** button.

The **Edit Categorization** pop-up opens.



5. Make sure **Assignable to Projects** is checked.
6. Click **OK** to close the **Edit Categorization** pop-up.
7. Click **OK** to close the **Configure Categorizations** pop-up.

The configured categorization can now be assigned to projects. In addition, a drop-down menu corresponding to the configured categorization now appears in the sidebar of the BEA AquaLogic Enterprise Repository **Projects** screen.

Projects

Name

Department
All Departments

Status
All Status

Line Of Business
All Lines Of Business

Search

Create New
List All


This drop-down can be used to filter project searches.

8. Repeat the **Configure Categorizations** procedure as necessary to add other categorizations for use with projects.


Assigning a Categorization to a Project

This procedure is performed on the BEA AquaLogic Enterprise Repository **Projects** screen.

1. Select a project to which the categorization will be assigned.
2. Click the **Edit** button in the project detail.



The **Edit Project** pop-up opens.




3. Locate the **Categorizations** section in the **Edit Project** pop-up.



Note that the available categorization in the example corresponds to the previously **configured categorization**.

4. Click the **Edit** button.

The **Categorization Selection** pop-up opens.




Note that the **Categorization Selection** pop-up is labeled according to the previously **configured categorization, Lines of Business**.

5. Select the categorization to be assigned to the project from the **Available Categorizations** list in the pop-up.
6. Use the >> button to move the chosen categorizations to the **Selected Categorizations** list.
7. Click **OK**.
8. The selected categorization now appears in the **Categorizations** section in the **Edit Project** pop-up.



9. Click **Save** to close the **Edit Project** pop-up.

The selected categorization now appears in the project detail.



Access Settings

Access Settings allow the administrator to assign permissions to each role. Access settings identify the functions and responsibilities of a role, and determine each role's level of access to assets and asset management features in AquaLogic Enterprise Repository (ALER).

System safeguards prevent an administrator from inadvertently modifying permissions in such a way that would prevent his/her subsequent access to **Access Settings**.

- **Basic Access Settings (BAS)**
 - Control the access to assets in AquaLogic Enterprise Repository across the board, based on the roles to which users are assigned. Access to ALER tools, such as the **Asset Editor** or the **Type Manager**, is similarly controlled. Basic Access Settings establish access across the system. For example, permission to view assets applies to all assets; as does permission to **Use/Download** assets.
- **Custom Access Settings (CAS)**
 - Establish Advanced Role-based Access Control to restrict access to specific assets or groups of assets in AquaLogic Enterprise Repository to specific user roles.

Security Considerations

Role-based Access Control (RBAC) allows AquaLogic Enterprise Repository to track asset usage and production on a by-user basis and personalizes the presentation of assets, limiting visibility to designated portions of AquaLogic Enterprise Repository. **However, Role-based Access Control is not intended to provide security for asset metadata, nor is it intended to supplement the security of underlying asset repositories.**

AquaLogic Enterprise Repository access settings provide no additional security for otherwise unsecured assets or data. For maximum security, asset metadata should be managed in a manner that prevents access to the metadata via an unsecured repository. Confidential information should be embedded in the asset's payload, or attached as documentation files and hosted in a secure repository.

If you choose to circumvent an authentication and permission challenge from the underlying asset repository, you do so at your own risk.

The following actions also have security implications:

- Configuring SCM systems for access via a single AquaLogic Enterprise Repository user account

- Allowing system access by unapproved users
- Creating guest account logins
 - Guest accounts are strictly forbidden under the AquaLogic Enterprise Repository license.

Any of these actions has the potential to open the contents of AquaLogic Enterprise Repository to anyone with network access to ALER.

Access Settings and the Asset Editor

Depending on the **Access Settings** in use, users with access to the **Asset Editor** may be able to see relationships to assets that are otherwise invisible to them in the registry. In this situation, the name of the hidden asset is visible, as is the detail of the relationship between that asset and an asset to which the users have access. No other information on the hidden asset is visible in the Asset Editor. In this situation, it is possible to delete the relationship between the visible and the hidden asset. However, given that the invisible asset is inaccessible to the users in question, the relationship cannot be restored by those users.

Permissions

Permissions may be:

- **Granted** (Permission is explicitly granted)
- **Denied** (Permission is explicitly denied)
- **Not Granted** (Permission is not explicitly granted nor denied.)

The table below identifies permissions that may be managed within **Basic Access Settings**.

Access Definitions

Assets: Tools regulated: ALER **Asset** screen, **Asset Editor**, **Type Manager**.

Permission	Description
View	Assets may be viewed in ALER.
Use	Displays/enables the Use - Download button in ALER.
Download	Asset files may be downloaded. Provides visibility to file links after pressing the Use - Download button.
Review	Reviewing assets using ALER.
Edit	Editing assets in the Asset Editor .

Accept	Accepting assets. This button, in the Asset Editor , moves assets from the Submitted -- Pending Review to the Submitted -- Under Review queue.
Approve Tabs	Approving metadata for assets. This button is available at the bottom of each tab in the Asset Editor display of each asset. Approving a tab logs the name of the approver and the date in the metadata, moves the asset out of the Submitted - Under Review queue for that tab, and changes the tab's text label to green.
Register	Registering assets. This permission provides the user with the ability to register all assets in the Asset Editor .
Edit Access Settings	Applicable only with Custom Access Settings . Provides the ability to change Custom Access Settings permissions on all assets.
Create/Submit	Gives a user the ability to submit assets through or create new assets through the Asset Editor .
Launch Asset Editor	Gives a user the ability to open the Asset Editor tool. One must use this tool to edit and register assets.
Edit Artifact Stores	Gives a user the ability to create and edit artifact stores (through the Asset Editor).
Edit Types	Gives a user the ability to configure asset type/compliance template metadata. Requires the Launch Asset Editor permission.
Notify	Determines if the user is allowed to send an ad-hoc email to users.
Global Permissions	These are permissions that do not apply to individual assets and cannot be overridden by custom access settings.

Access: Tools regulated: ALER **Admin** screen: **Users, Sessions, Roles, Departments, File Stores, Basic Access Settings, Custom Access Settings**

Permission	Description
View	Viewing entries in the sections noted above.
Edit	Editing entries in the sections noted above.
Create	Creating users, roles, departments, file stores, and custom access settings.
Delete	Deleting sessions, roles, and custom access settings.

Projects: Tools regulated: ALER **Projects** screen

Permission	Description
View	Viewing projects on the Projects page.
Edit	Editing projects on the Projects page.
Create	Creating projects on the Projects page.
Apply Template	Apply a compliance template to a project.

Policies: Tools regulated: ALER **Asset** screen

Permission	Description
Apply Policy	Allows user to apply a policy to other assets.

Reports: Tools regulated: ALER **Reports** screen

Permission	Description
View	Viewing reports.


System Administration: Tools regulated: ALER **Admin** screen: **System Settings, Email Templates.**

Permission	Description
Edit	Ability to edit general, security, authentication, and file store settings.
Enable	Ability to enable new general, security, authentication, and file store settings.


Granting Permissions to a Role

This procedure is performed on the AquaLogic Enterprise Repository **Admin** screen.

1. In the left panel, click **Basic Access Settings**.
2. Select the appropriate grouping from the list in the **Basic Access Settings** section.




The selected grouping's access settings are displayed in the main pane.



3. Click the **Edit** button (upper right corner of the main pane.)

The **Edit Basic Access Settings for:...** pop-up opens.



Roles are listed on the left; Permissions are listed along the top.

4. Select the appropriate radio button to determine which roles are displayed.



5. Select the role to which permissions are to be granted.
6. Use the checkboxes to assign the appropriate permission.
 - o One click on an empty box adds a check mark (**Granted**)
 - o A second click adds an **X** (**Denied**).
 - o A third click clears the box (**Not Granted**).
7. When finished, click **Save**.

Editing Permissions

See: [Granting Permissions to a Role](#)


Verifying User Permissions

This procedure is performed on the AquaLogic Enterprise Repository **Admin** screen.

1. In the left panel, click **Basic Access Settings**.
2. Select the appropriate grouping from the list in the **Basic Access Settings** section.


The selected grouping's access settings are displayed in the main pane.
3. Click the **View Access** button (upper right corner of the main pane).

A message pop-up opens.



4. Click **Configure**.

The **Search / Filter Users and Access Settings** pop-up opens.




















5. Use **Search** or click **List All** in the **Find Users** section to locate the user(s) whose permissions are to be verified.
6. Use the >> button to move user(s) from the **Available Users** column to the **Selected Users** column.
7. Click **OK**.

The selected user's access settings are displayed.

View access for Basic Access Settings for "Assets"

Note: The displayed information reflects only Basic Access Settings for the indicated user, and does not reflect permissions assigned to the user by Custom Access Settings. Please click "Configure" to add Custom Access Settings to this evaluation.

Users/Roles	View	Use	Download	Review	Notify	Edit	Accept	Approve Table	Register	Edit Access Settings	Submit	Launch Asset Editor	Edit Artifact Stores	Edit Type
 Smith, John K.														

 Yes, user has permission
 No, user does not have permission
 * - user has the admin role and so has all permissions


8. If multiple users are selected, clicking the > icon next to a user's name will display information specific to that user.
9. When finished, click **Close**.

System Settings Overview

AquaLogic Enterprise Repository's **System Settings** section allows administrators to configure the basic ALER operation and to enable/disable specific features.


Access System Settings



1. Click **System Settings** in the sidebar on the ALER **Admin** screen.



The **System Settings** section opens in the main pane.

System Settings are organized into categories. These categories may vary based on licensing restrictions. Each category is further divided into feature groups.



2. Click  to expand the display of any category or feature group.
3. Click  to collapse the display.

Search for System Settings

System settings for particular features can be located using the System Settings **Search**.

1. Enter a search term in the System Settings **Search** box.

The relevant category sections expand to display the relevant System Settings.

Search

Functional Settings

Notifications

Asset Use Notification
 cmee.extraction.notify-maintainer True False
 Send email to the notification email address for used assets.

Default Email Address for Asset Use Notification
 cmee.extraction.default-maintainer.email
 Send email to this address if the notification email address is not set on an asset.

Registrar Email Address
 cmee.registrar.email
 Registrar's email address, to be used in auto-generated email messages.

Access Administrator Email Address
 cmee.securityadmin.email
 The email address to which user- and access-related auto-generated emails are sent. This includes notifications sent when unapproved LDAP users are added to the user directory.

Server Settings

Email

Default Email Suffix
 enterprise.defaults.email.suffix
 Suffix added to a username to determine their default email address.

Allow Distribution List Email
 cmee.email.cc True False
 Allow users to create distribution lists so that the members of the list are automatically copied on certain email notifications that are sent as part of the asset registration process.

Allow External Emails in a Distribution List
 cmee.email.nonuser.cc True False
 Allow users to provide external email addresses in their distribution lists for email notifications.

SMTP Server
 cmee.server.smtp
 The IP address of the SMTP server used for auto-generated email messages.

Use External Email System
 cmee.server.smtp.send-with-iron True False
 True = Uses external email system for notifications, False = Uses ALER internal email "send" mechanism for notifications. NOTE = Restart server after changing this setting.

Send Email Interval
 cmee.server.smtp.send-interval

2. Click the **Clear** button to clear the search results.

Enable System Settings Properties

In some cases it may be necessary to enable specific properties in order to activate certain optional ALER features. These properties will be provided by BEA Support.

1. Obtain the necessary system setting property.
2. Enter the system setting property in the **Enable New System Setting** text box.
3. Click **Enable**.

The appropriate System Setting category will open in the lower pane.

4. Edit the system setting properties as necessary.
5. Click **Save** when finished.

Move Settings to Database

Exercising this option moves all system settings stored in property files to the database. **This action cannot be reversed.**

1. Click **Move settings to database**. All system settings are saved to the database. This is for a clustered environment. All servers in the clustered environment will now have one source for system settings.


See the *ALER Clustering Guide* for more information (under the "Move Application Properties to the Database" section).

Functional Settings: General User Interface


General User Interface	
Full Name Format enterprise.defaults.fullname.format	<input type="text" value="{last} {first} {middle}"/> The format used for the full names in the system. This can contain the strings "{prefix}", "{first}", "{middle}", "{suffix}" and punctuation immediately following any of these name parts in any order. Extra space is trimmed. NOTE-Restart server after changing this setting.
Display Name Field enterprise.defaults.displayname.field	<input type="text" value="fullname"/> Field to display for user. NOTE-Restart server after changing this setting.
Display Name - Full Name and Initial enterprise.defaults.fullname.middleasinitial	<input checked="" type="radio"/> True <input type="radio"/> False Enables display of a full name and middle initial for the display name where visible.
Default Browse Categorization cmee.assettab.default-categorization	<input type="text" value="AssetFunction"/> The categorization type initially used to group items in the Browse Assets tree.
Show Browse Asset Tree cmee.assettab.browse.visible	<input checked="" type="radio"/> True <input type="radio"/> False Enables the browse asset tree, sortable by asset categorization.
Default Browse Type cmee.assettab.default/categorization/show-assettype	<input type="radio"/> True <input checked="" type="radio"/> False Enables the default browse to show types.
Sticky Registrar Queues cmee.registrar.stickyqueues	<input checked="" type="radio"/> True <input type="radio"/> False The currently displayed tab in the Asset Editor remains selected when browsing from one asset to another.
Table Zoom cmee.assettab.multiplegroupselement.force-zoom	<input type="radio"/> True <input checked="" type="radio"/> False Enables table elements to open in their own window
Repeat Table Header cmee.assettab.multiplegroupselement.show-header-interval	<input type="text" value="0"/> Interval to repeat the table header within large tables. Specified in number of rows.
Show All Detail In Tabs cmee.framework.show-as-tabs	<input type="radio"/> True <input checked="" type="radio"/> False Make the default detail screen view to be a tabbed view.
Long Date Format Specification cmee.server.date.format.long.default	<input type="text" value="yyy-MM-dd HH:mm:ss z"/> Specifies the date format for the display of full date information (year, month, day, time, timezone, etc.) in the application. For example, to display dates in European format, enter "dd-MM-yyyy HH:mm:ss Z". See product documentation for full formatting syntax.
Short Date Format Specification cmee.server.date.format.short.default	<input type="text" value="yyy-MM-dd"/> Specifies the date format for the display of abbreviated date information (year, month, day) in the application. For example, to display dates in European format, enter "dd-MM-yyyy". See product documentation for full formatting syntax.
Show System-Supplied Relationships cmee.show-system-supplied-relationships	<input checked="" type="radio"/> True <input type="radio"/> False Allows users to see system-supplied relationships and relationship types.

Properties

- **Default Browse Categorization**
 - cmee.assettab.default-categorization
 - The drop-down menu selection determines the initial asset categorization in the **Browse Tree** on the **Assets** screen.




Results in...



- **Default Browse Type**

- `cmee.assettab.default-categorization-show-assettype`
- The **True** and **False** radio buttons toggle the default display of assets by Type in the **Browse Tree** on the **Assets** screen (subject to the system setting in **Default Browse Categorization**).

True results in...



- **Sticky Registrar Queues**

- `cmeeregistrar.stickyqueues`
- The **True** and **False** radio buttons toggle the default display of the selected **Asset Editor** tab when browsing assets.
 - **True:** Each asset opens to the Asset Editor tab in view from the previously selected asset.
 - **False:** Defaults to the **Overview** tab for each asset viewed in the **Asset Editor**.

- **Table Zoom**

- `cmeeregistrar.multiplegroupelement.force-zoom`
- The **True** and **False** radio buttons toggle the ability to open table elements in their own window.

- **Repeat Table Header**

- `cmeeregistrar.multiplegroupelement.show-header-interval`
- The number entered in the text box determines the interval (number of rows) at which the table header repeats in large tables.
 - Value of 0 results in...

Cost Categories		
Total Projected Fiscal Year Costs: 302610		
Actual Costs (YTD): 250680		
Annual Costs (Detail):		
Cost Category	Projected	Actual
Development	55450	61230
Operations	98600	98600
Maintenance	98560	90850
Support	50000	0
Lifecycle Investment to Date (Total Cost of Ownership): 970500		
Cost Per Transaction (\$): 0.27		
Chargeback Costs: 100% of cumulative transaction costs		


- Value of 2 results in...

Cost Categories		
Total Projected Fiscal Year Costs: 325000		
Actual Costs (YTD): 334700		
Annual Costs (Detail):		
Cost Category	Projected	Actual
Development	75000	81200
Operations	100000	104900
Cost Category	Projected	Actual
Maintenance	100000	98600
Support	50000	50000
Lifecycle Investment to Date (Total Cost of Ownership): 1250000		
Cost Per Transaction (\$): 0.31		
Chargeback Costs: 100% of cumulative transaction costs		


- **Show All Detail In Tabs**

- o `cmeeframework.show-as-tabs`
- o The **True** and **False** radio buttons toggle the default display of the asset detail.

- **True** results in the tabbed view...




- False results in the standard view...



- Long Date Format Specification

- `cme.server.date.format.long.default`
- Specifies the date format for the display of full date information (yyyy-MM-dd HH:mm:ss z).

Results in...



- Short Date Format Specification

- `cme.server.date.format.short.default`
- Specifies the date format for the display of abbreviated date information (yyyy-MM-dd).
 - Similar to Long Date Format Specification.

- Full Name Format

- `enterprise.defaults.fullname.format`
- Specifies the format for the display of user names. Can contain the strings "{prefix}", "{first}", "{middle}", "{suffix}" and punctuation immediately following any of these name parts in any order. Extra space is trimmed.
 - **Note:** Changes to this setting require server restart.

Results in...

User Name	Display Name	Status
jsmith	Smith, John J.	Active


- **Show System-Supplied Relationships**

- `cmee.show-system-supplied-relationships`
- The **True** and **False** radio buttons toggle the display of system-supplied relationships in the **Asset Editor** tab and in the asset detail. The **False** setting will hide system-supplied relationships in the Asset Editor's **Relationships** tab and in the asset detail; however, they will remain visible in the Asset Editor's **Configure Relationships** dialog.

System-supplied relationships are used for system-specific relationships within ALER, such as allowing for more complex matches when doing asset updates. Therefore, users cannot create or delete system-supplied relationships, nor can they modify a system-supplied relationship's direction, which is always read-only.

- **Display Name Field**

- `enterprise.defaults.displayname.field`
- Drop-down menu selection determines the information displayed for the user.
 - **Note:** Changes to this setting require server restart.



Results in...

User Name	Display Name	Status
jsmith	Smith, John J.	Active

- **Display Name - Full Name and Initial**

- `enterprise.defaults.fullname.middleasinitial`
- When a user's middle name is supplied, the **True** and **False** radio buttons toggle the display of the middle name in full or as an initial.

True results in...

<u>User Name</u>	<u>Display Name</u>	<u>Status</u>
jsmith	Smith, John James	Active

False results in...

<u>User Name</u>	<u>Display Name</u>	<u>Status</u>
jsmith	Smith, John J.	Active

Functional Settings: Search


Search	
Save Searches cmee.asset.registry.saved.searches	<input checked="" type="radio"/> True <input type="radio"/> False Enables the ability to save search criteria.
Search Indexed Fields cmee.search.general.include.indexedfields	<input checked="" type="radio"/> True <input type="radio"/> False Include indexed fields in general Asset Searches
Search Categorizations cmee.search.general.include.categorizations	<input checked="" type="radio"/> True <input type="radio"/> False Include categorizations in general Asset Searches
Advanced Search Categorization Default Visibility cmee.search.advanced.categorizations.visible	<input type="radio"/> True <input checked="" type="radio"/> False If true then categorizations in the advanced search window will be initially expanded and included in the search.
Search Specific Field cmee.search.specific.field	<input checked="" type="radio"/> True <input type="radio"/> False Enables the ability to enter in a field name (followed by a ':') into the keyword search and search on that specific field.
Confirm Empty Search cmee.empty.search.confirm	<input type="radio"/> True <input checked="" type="radio"/> False Forces a warning when a user searches on a blank string.
Assembly Model Visibility cmee.assembly.model.visibility	<input checked="" type="radio"/> True <input type="radio"/> False Provides the ability to filter out Assembly Models

Properties

- **Save Searches**

- cmee.asset.registry.saved.searches
- The **True** and **False** radio buttons toggle the **Save Searches** feature. This feature allows search criteria to be saved and reused.

True displays the **Saved Searches** section in the sidebar on the **Assets** screen, as illustrated below.



- **Search Indexed Fields**

- cmee.search.general.include.indexedfields
- The **True** and **False** radio buttons toggle the inclusion of indexed fields in general asset searches.

- **Search Categorizations**

- cmee.search.general.include.categorizations
- The **True** and **False** radio buttons toggle the inclusion of categorizations in general asset searches.

- **More Search Options Categorization Default Visibility**

- cmee.search.advanced.categorizations.visible
- The **True** and **False** radio buttons toggle the default display of the Categorizations tree in the More Search Options pop-up.

False results in...

True results in...

- **Search Specific Field**

- `cmee.search.specific.field`
- The **True** and **False** radio buttons toggle the ability to search specific fields during Standard Searches by identifying the field to be searched in the Keyword text box.

As illustrated below, the string `description:MyAsset` will search for the keyword the **MyAsset** in the **Description** field of every asset in the Repository.

Search

Enter Search String (?)
description: MyAsset

Type
All Types

Asset Function
All Asset Functions

[More Search Options](#)

Search

- **Confirm Empty Search**

- `cmee.empty.search.confirm`
- The **True** and **False** radio buttons toggle the display of a warning message when a user performs a search on a blank string.

True displays a warning message.

- **Minimum Number of Characters for User Search**

- `cmee.users.min.text.search`
- The numerical value entered in the text box determines the minimum number of characters required to perform a search to locate user information.

Attempts to perform a user search with fewer than the minimum number of characters results in a warning message.

Functional Settings: Projects and Navigator

Projects and Navigator	
Enable Projects cmee.projects.enabled	<input checked="" type="radio"/> True <input type="radio"/> False Enables the support of multiple projects
Navigator & Project Hierarchy cmee.projecttool.advanced	<input checked="" type="radio"/> True <input type="radio"/> False Enables advanced project options including the navigator and project hierarchy
Navigator Support for Microsoft JDK cmee.navigator.force-msjdk-support	<input type="radio"/> True <input checked="" type="radio"/> False Uses alternative navigator applet which is compatible with Microsoft's applet plugin for Internet Explorer.
User Defined Projects cmee.extraction.user-projects.enable	<input type="radio"/> True <input checked="" type="radio"/> False Enables users to create their own projects feature during asset usage.
User Defined Projects - Prefix cmee.extraction.user-projects.prefix	<input type="text" value=""/> Prefix used with the user name to determine the project name for the user defined project. (Useful for visual grouping in reports.)
Producing Projects cmee.project.producing.enabled	<input checked="" type="radio"/> True <input type="radio"/> False Enables capture of producing projects for assets.
Advanced Project Option - Categorization cmee.projecttool.categorizations	<input checked="" type="radio"/> True <input type="radio"/> False Enables the assignment of categorizations to projects

Properties

- **Navigator and Project Hierarchy**
 - cmee.projecttool.advanced
 - The **True** and **False** radio buttons toggle advanced project options including the **Navigator** and project hierarchy.
- **Navigator Support for Microsoft JDK**
 - cmee.navigator.force-msjdk-support
 - The **True** and **False** radio buttons toggle the use of an alternative Navigator applet that is compatible with Microsoft's applet plugin for Internet Explorer.
- **User Defined Projects**
 - cmee.extraction.user-projects.enable
 - The **True** and **False** radio buttons toggle the feature that allows users to create a project on the fly during the asset **Use/Download** process.

True results in...

Use - Download

Sample Comm Adapter - Customer Credit Information (3.0)

Please Choose a Project

Or

Create a new project

Project Name

(will be prefixed by: Smith, Joe)

Department Please Choose a Department

Subscriptions for Sample Comm Adapter - Customer Credit Information (3.0)

Send me information updates about this asset.

Assets Related to Sample Comm Adapter - Customer Credit Information (3.0)

No related assets that may also be used were found.

False results in...

Use - Download

Sample Comm Adapter - Customer Credit Information (3.0)

Please Choose a Project

Subscriptions for Sample Comm Adapter - Customer Credit Information (3.0)

Send me information updates about this asset.

Assets Related to Sample Comm Adapter - Customer Credit Information (3.0)

No related assets that may also be used were found.

- **User Defined Projects - Prefix**

- `cmeextraction.user-projects.prefix`
- As illustrated below, text entered in the property text box becomes the prefix for any user-defined projects. This is useful for visual grouping in reports. (User-defined Projects must be enabled.)

example



Prefix used with the user name to determine the project name for the user defined

Results in...

Use - Download

You have selected the following items for use in **example Smith, Joe - MyProject**. After you evaluate these items, please remember to update their usage status in My Stuff.

Listed below are the downloadable files associated with your asset usage.

Sample Application - Commercial Card Authorization System	Get File
License Key - This is the license key that will allow installation of the application	 

- **Producing Projects**

- `cmee.project.producing.enabled`
- The **True** and **False** radio buttons toggle the display of the **Producing Projects** section in the **Asset Submission** pop-up (**Standard Submission** via the **Submit and Asset** link on the **ALER Assets** screen.)

True results in...

Asset Submission

Overview

Type*: ▾

Name*:

Version:

Description*:
(Max 4000 Characters)

Comments:
(Max 4000 Characters)

Producing Projects

Available Projects		Selected Projects
Regdy	<input type="button" value="→"/> <input type="button" value="←"/> <input type="button" value="All →"/> <input type="button" value="All ←"/>	

File Information

File's Location URL*:

Attack file by reference - Changes made to the file in its original location are reflected immediately.

Submitted By: Admin, Repository

Submission Date: 2007-06-19

*Denotes required field

False results in...

Asset Submission

Overview

Type*: ▾

Name*:

Version:

Description*:
(Max 4000 Characters)

Comments:
(Max 4000 Characters)

File Information

File's Location URL*:

Attack file by reference - Changes made to the file in its original location are reflected immediately.

Submitted By: Smith, Joe

Submission Date: 2007-06-19

*Denotes required field

Functional Settings: Notifications

Notifications	
Asset Use Notification cme.e.extraction.notify-maintainer	<input checked="" type="radio"/> True <input type="radio"/> False Send email to the notification email address for used assets.
Default Email Address for Asset Use Notification cme.e.extraction.default.maintainer.email	<input type="text" value=""/> Send email to this address if the notification email address is not set on an asset.
System Registrar Email cme.e.registrar.email	<input type="text" value="REGISTRAR_EMAIL"/> System Registrar's email address, to be used in auto-generated email messages.
System Registrar Alternate Notification cme.e.registrar.email.enable	<input checked="" type="radio"/> True <input type="radio"/> False Allows notification emails to be sent to the System Registrar email address when the notification email has not been set on an asset.
Access Administrator Email Address cme.e.security-admin.email	<input type="text" value="SECURITY_EMAIL"/> The email address to which user and asset-related auto-generated emails are sent. This includes notifications sent when unapproved LDAP users are added to the user directory.
Enable Reminder Email cme.e.extraction.notification.enabled	<input checked="" type="radio"/> True <input type="radio"/> False Enables notification via email to update the status of asset usage and value metrics.
Reminder Delay cme.e.extraction.initial.delay	<input type="text" value="INITIAL_DELAY"/> The number of days to wait after a user downloads an asset before sending a reminder to update the status of that usage.
Reminder Delay - Subsequent cme.e.extraction.subsequent.delay	<input type="text" value="SUBSEQUENT_DELAY"/> The number of days to wait after sending the initial usage status reminder message before subsequent reminders are sent.

Properties

- **Asset Use Notification**

- cme.e.extraction.notify-maintainer
- The **True** and **False** radio buttons toggle the feature that automatically sends an email to the notification address listed for an asset when that asset is used.

Miscellaneous

Notification Email: user@example.com

Source/Vendor/Service Provider: [Service Provider]

Organizational Ownership: [Owner 1]

Licensing/License Type: This service must be licensed

Usage Fee: 6000.0

Currency: USD United States Dollars

- When an email is sent, the following algorithm is used to determine the destination address:
 1. If the asset has a notification address, use that as the email destination,
 2. else, if the system setting cme.e.extraction.default.maintainer.email has a value, use that value as the destination address,
 3. else, if there is a "submitted-by" user that has an email address, use that email address,
 4. else, if there is a "created-by" user that has an email address, use that email address,

5. else, do not send a usage notification email.

- **Default Email Address for Asset Use Notification**

- `cmee.extraction.default.maintainer.email`
- This system setting is used to specify the default destination email address for notifications related to usage sent by the system.

- **System Registrar Email**

- `cmee.registrar.email`
- Fill in the text box with the registrar's email address, to be used in auto-generated email messages.

- **System Registrar Alternate Notification**

- `cmee.registrar.email.enable`
- Allows notification emails to be sent to the System Registrar email address when the notification email has not been set on an asset.

- **Access Administrator Email Address**

- `cmee.security-admin.email`
- Fill in the text box with the email address of the individual(s) to whom user- and access-related auto-generated emails are to be sent. This includes notifications sent when unapproved LDAP users are added to the user directory.

- **Enable Reminder Email**

- `cmee.extraction.notification.enabled`
- Enables notification via email to update the status of asset usage and value metrics.

- **Reminder Delay**

- `cmee.extraction.initial.delay`
- Fill in the text box with a numeric value indicating the number of days to wait after a user downloads an asset before sending a reminder to complete the **Update Status** form (see below).

Update Status

You recently used **Sample Application - Commercial Card Authorization System** to evaluate it for use in **example Smith, Joe - MyProject**. Your feedback is an essential resource to other developers who may wish to use this asset in the future. Please update the usage status of this asset below:

Status:

- **Reminder Delay - Subsequent**

- `cmee.extraction.subsequent.delay`
- Fill in the text box with a numeric value indicating the number of days to wait after the initial usage status reminder message before sending subsequent reminders.

Functional Settings: Use - Download


Properties

- **Asset Usage Custom Field List**

- `cmee.extraction.exported-custom-field`
- This unique setting allows the creation of Custom Asset Usage Fields.

Create Custom Usage Fields

1. Enter a name for the Custom Usage Field in the text box.
2. As necessary, click **Add** to open additional text boxes.



The screenshot shows a window titled "Use - Download". It contains two main sections:

- Asset Usage Custom File**
`cmee.extraction.export.filename`
Filename to save custom asset metadata fields from asset download pane.
- Asset Usage Custom Field List**
`cmee.extraction.exported-custom-field.`
List of custom usage fields to save to the file.

The "Asset Usage Custom Field List" section has two text boxes containing "CustomField_1" and "CustomField_2". Below these boxes is an "Add (+)" button.

3. Enter a name for each additional Custom Usage Field in the corresponding text box.
4. Click **Save** when finished.

The new Custom Usage Fields appear in the **Use - Download** pop-up.

Use - Download

Sample Application - Commercial Card Authorization System

Please Choose a Project

Or

Create a new project

Project Name

(will be prefixed by: example Smith, Joe)

Department

CustomField_1:

CustomField_2:

Subscriptions for Sample Application - Commercial Card Authorization System

Functional Settings: Custom Links

Custom Links	
Custom Link 1 cmee.tool.show-marketplace	<input checked="" type="radio"/> True <input type="radio"/> False Enables the display of the Custom Link 1.
Custom Link 1 Label cmee.tool.marketplace.label	Custom 1 Specifies a custom label for the Custom Link 1
Custom Link 1 URL cmee.tool.marketplace.url	http://www.example1.com Specifies a custom URL for the Custom Link 1.
Custom Link 1 Target Frame cmee.tool.marketplace.target	custom1 Specifies the frame in which to open Custom Link 1
Custom Link 2 cmee.tool.show-resource	<input checked="" type="radio"/> True <input type="radio"/> False Enables the display of the Custom Link 2 link.
Custom Link 2 Label cmee.tool.resource.label	Custom 2 Specifies a custom label for the Custom Link 2 link
Custom Link 2 URL cmee.tool.resource.url	http://www.example2.com Specifies a custom URL for the Custom Link 2 link.
Custom Link 2 Target Frame cmee.tool.resource.target	custom2 Specifies the frame in which to open the Custom Link 2 link
Custom Help URL cmee.tool.help.url	http://javacm.flashline.com/ficmee/aler30/help/wwhelp.htm Specifies a custom URL for the Help link.


This group of settings controls the configuration and display of custom links on the right side of the AquaLogic Enterprise Repository menu bar.

Properties


- **Custom Link 1**

- cmee.tool.show-marketplace
- The **True** and **False** radio buttons toggle the display of Custom Link 1.

False results in...



True results in...



(Illustrates both **Custom 1 Link** and **Custom 2 Link** set to **True**.)

- **Custom Link 1 Label**

- cmee.tool.marketplace.label
- Text entered in the text box will appear as the label for Custom Link 1 on the ALER menu bar.

- **Custom Link 1 URL**
 - `cme.tool.marketplace.url`
 - Enter the URL for Custom Link 1.
- **Custom Link 1 Target Frame**
 - `cme.tool.marketplace.target`
 - Specifies the frame in which to open Custom Link 1.
- **Custom Link 2**
 - `cme.tool.show-marketplace`
 - The **True** and **False** radio buttons toggle the display of Custom Link 2.
- **Custom Link 2 Label**
 - `cme.tool.marketplace.label`
 - Text entered in the text box will appear as the label for Custom Link 2 on the ALER menu bar.
- **Custom Link 2 URL**
 - `cme.tool.marketplace.url`
 - Enter the URL for Custom Link 2.
- **Custom Link 2 Target Frame**
 - `cme.tool.marketplace.target`
 - Specifies the frame in which to open Custom Link 2.
- **Custom Help URL**
 - `cme.tool.help.url`
 - Specifies a custom URL for the Help link.
 - Note: ALER help files are hosted remotely by default. If necessary, Help files can be hosted in your local environment. Change this setting to reflect the location of the Help files.

Functional Settings: Reports



Properties

- **Enable PDF Output For Reports**

- `cmee.reports.pdf.enable`
- Default setting is **False**.
- **IMPORTANT:**
 - **DO NOT** set to **True** if the database in use has been configured to use the Unicode/UTF-8 character set.

The ALER reporting engine does not support the Unicode/UTF-8 character set. Attempts to export reports to PDF using this character set will result in missing data.

- **Enable Excel Output For Reports**

- `cmee.reports.excel.enable`
- The **True** and **False** radio buttons toggle the ability to export reports in Microsoft Excel format.

Functional Settings: Miscellaneous

Miscellaneous	
Consumer Survey cmee.extraction.consumer-survey.enable	<input checked="" type="radio"/> True <input type="radio"/> False Enables consumer survey of asset value on usage
Default Usage Rejection Reason cmee.default.usage.rejection.reason	Other This is the default rejection reason to be used when an asset usage is rejected from a project via the Project Edit window.
Export Assets into a Microsoft Excel spreadsheet cmee.asset-registry.export.excel	<input checked="" type="radio"/> True <input type="radio"/> False Allows Assets to be exported to an external Microsoft Excel file.
Affinity Threshold cmee.assettab.affinity.threshold	1 The threshold value to use when determining which affinity assets should be displayed on an asset detail page.
Affinity Minimum Project Count cmee.assettab.affinity.minimum	-1 Minimum number of projects to require inclusion in for assets to appear in Affinity section on asset detail page.

Properties

- **Asset Submission File Requirement**

- cmee.submission.file.required.enable
- When enabled, a user performing a Standard Asset Submission will be required to provide a file location URL or upload files.

- **Consumer Survey**

- cmee.extraction.consumer-survey.enable
- The **True** and **False** radio buttons toggle the display of the complete asset usage **Update Survey**, available for any asset listed in the **Asset Usage** section of the **My Stuff** page.

True displays the full survey...

Update Status

You recently used **Sample Application - Commercial Card Authorization System** to evaluate it for use in **example Smith, Joe - MyProject**. Your feedback is an essential resource to other developers who may wish to use this asset in the future. Please update the usage status of this asset below:

Status:

The predicted net hours saved when using this asset is **0.0**

1. As a Consumer of this asset, have you found value in it?

Yes

No

False displays only the **Status** drop-down menu.

Update Status

You recently used **Sample Application - Commercial Card Authorization System** to evaluate it for use in **example Smith, Joe - MyProject**. Your feedback is an essential resource to other developers who may wish to use this asset in the future. Please update the usage status of this asset below:

Status:

- **Default Usage Rejection Reason**


- `cme.e.default.usage.rejection.reason`
- Use the drop-down menu to select the default asset rejection reason that will be recorded when an asset is rejected when updating the status of the asset usage in the **My Stuff** section.

Consumed Assets	
Consumed Asset	Used By
<input type="checkbox"/> Sample Application - Commercial Card Authorization System	Smith, Joe

- **Export Assets into a Microsoft Excel spreadsheet**

- `cme.e.asset.registry.export.excel`
- The **True** and **False** radio buttons toggle the ability to to export asset detail information to an external Microsoft Excel spreadsheet.

True displays the **Export to Excel** menu selection in the asset search results frame and the **Excel** button in the asset detail.




False removes the menu selection and button.

Affinity Settings

Within the context of ALER, **Affinity** is the condition that occurs when two or more assets are deployed in the same project. The **Affinity** element will appear in the asset detail for each asset that meets this condition, and will list other assets that have (deployed) projects in common.


The following **Affinity** System Settings determine the specific behaviour of the **Affinity** element and its contents.

- **Affinity Threshold**
 - `cme.assettab.affinity.threshold`
 - If the number of affinity matches exceeds the numerical value entered for this setting, a **View All Affinity Assets** link appears in the **Affinity** element in the asset detail.
- **Affinity Minimum Project Count**
 - `cme.assettab.affinity.minimum`
 - The numerical value entered in this field determines the minimum number of projects to which an asset is deployed in order to be displayed in the **Affinity** element in the asset detail.



If the number of projects that have consumed the asset is less than the supplied numerical

value, the **Affinity** element will indicate that the display criteria have not been met:

A rectangular notification box with a blue header and a white body. The header contains the word "Affinity" in white text. The body contains the text "No affinity references match display criteria." in black, followed by a link "View All Affinity Assets" in blue.

Affinity

No affinity references match display
criteria.

[View All Affinity Assets](#)

Server Settings: General

General	
Admin Role enterprise.security.roletype.admin	admin Role that enables a user to have admin rights (all permissions).
Company Name cmee.server.companyname	<COMPANY_NAME> The name of your company.
Homepage cmee.enterprisetab.homepage	http://lucloqap04.flashline.com:8080/qa070619/custom.home.jsp The URL displayed in the right frame as the home page.
Default Character Encoding cmee.server.defaultencoding	ISO-8859-1 The default character encoding to use in the system (defaults to the JVM default).
Enable Custom Unique Element cmee.unique-element.enable	<input checked="" type="radio"/> True <input type="radio"/> False Enables an additional plug-in for Types which defines a unique constraint additional to the name/version pair used by default.
Unique Element Per Type cmee.unique-element.per-assettype	<input type="radio"/> True <input checked="" type="radio"/> False Makes the Unique Element plugin pertain to each Type individually.

- **Company Name**
 - cmee.server.companyname
 - Enter the name of your company in the text box.
- **Homepage**
 - cmee.enterprisetab.homepage
 - The default URL points to the default ALER homepage, as it appears in the main (right) frame.

SOA Governance Starts Here

Right from the Start: SOA Lifecycle Governance
This paper explains why effective SOA governance throughout the SOA lifecycle can help your organization achieve measurable, sustainable business value from SOA.

Blog: Governance, Reuse, SOA and more
Opinion, advice, and community discussion on these and other important issues.

Webinar: Beyond Blueprints: From Vision to Value with SOA Governance
This presentation focuses on the people, practices, and technologies required for an effective SOA governance framework.

The diagram illustrates the SOA lifecycle governance framework. At the top is 'Business Strategy', which branches into 'Enterprise Architecture / SOA' and 'Business Process'. Below these are 'Model', 'Business Service', and 'Partner'. The central part shows 'Web Service' and 'Web Service' connected to 'Web Service' and 'Web Service'. At the bottom are 'Web Service', 'Web Service', and 'Web Service'. The diagram is signed 'J. Enrique'.

Application Assembly and Reuse

- Application Assembly: What's in it for you?
- Frequently Asked Questions
- Learn more about Service Component Architecture (SCA)
- Download the SCA Datapack

Information Resources

SOA Resource Center
The surest way to a fast, successful SOA implementation.

BEA AquaLogic™ Product Family
Service Infrastructure for managing SOAs in heterogeneous IT environments.

Hot Assets
No assets have been deployed yet.

High Interest
No assets have been used yet.

Newly Registered Assets
No assets have been registered yet.

Reuse Champs
No assets have been deployed yet.

Popular Searches
No searches have been performed yet.

Community Resources

- Dev2Dev
- Arch2Arch
- IT2IT

Change this URL as necessary to load a different page as the ALER homepage.

- **Default Character Encoding**

- `cmee.server.defaultencoding`
- The default character encoding to use in the system (defaults to the JVM default).
- Examples are UTF-8 and ISO-8859-1. UTF-16 is not supported.

- **Admin Role**

- `enterprise.security.roletype.admin`
- The text entered in this box designates the name applied to the role that has unlimited administrative rights and permissions within ALER.

Server Settings: Server Resources

Server Resources	
Database Connection Name enterprise.dbaccess.connectionname	enterprise The database connection name.
WebApp JSP Path enterprise.server.paths.jsp	[cmeeserverpaths\jsp] The application server path to the location where JSPs are stored.
WebApp Servlet Path enterprise.server.paths.servlet	[cmeeserverpaths\servlet] The application server path to the location where the servlets are hosted.
Web Resource Path cmeeserver.paths.resource	http://ucloasap04.fasline.com:8080/qa270613/web The Web server path to the location where Web resources are stored.
Web Image Path cmeeserver.paths.image	http://ucloasap04.fasline.com:8080/qa270613/web/images The Web server path to the location where some product images are stored. This must be the "images" subdirectory of the Web Resource Path.
Web JNLP Path cmeeserver.paths.jnlp-tool	http://ucloasap04.fasline.com:8080/qa270613/web/webstart The Web server path to the location where JNLP tool jars are stored. This path cannot point to an SSL-enabled service due to compatibility issues with Java Web Start.
WebApp JSP Path cmeeserver.paths.jsp	http://ucloasap04.fasline.com:8080/qa270613 The application server path to the location where JSPs are stored.
WebApp Servlet Path cmeeserver.paths.servlet	http://ucloasap04.fasline.com:8080/qa270613 The application server path to the location where product servlets are stored.
Asset Detail Path cmees.assettab.asset-detail-page	http://ucloasap04.fasline.com:8080/qa270613/cmees/index.jsp The application server path used by integrations to load asset details.

- **Web Resource Path**
 - `cmeeserver.paths.resource`
 - The filepath to the location on the Web server Web resources are stored.
- **Web Image Path**
 - `cmeeserver.paths.image`
 - The filepath to the location on the Web server where product images are stored. This setting must include the *images subdirectory of the Web Resource Path.
- **Web JNLP Path**
 - `cmeeserver.paths.jnlp-tool`
 - The filepath to the location on the Web server where JNLP tool jars are stored. Due to Java Web Start compatibility issues, this path must not point to an SSL-enabled service.
- **WebApp JSP Path**
 - `cmeeserver.paths.jsp`
 - The filepath to the location on the application server where JSPs are stored.
- **WebApp Servlet Path**
 - `cmeeserver.paths.servlet`
 - The filepath to the location on the application server where product servlets are stored.
- **Asset Detail Path**
 - `cmees.assettab.asset-detail-page`
 - The application server path used by integrations to load asset details.
- **Database Connection Name**
 - `enterprise.dbaccess.connectionname`
 - The name assigned to the database connection.
- **WebApp JSP Path**

- `enterprise.server.paths.jsp`
- The filepath to the location on the application server where JSPs are stored.

- **WebApp Servlet Path**

- `enterprise.server.paths.servlet`
- The filepath to the location on the application server where the servlets are hosted.

Server Settings: Email

Email	
Default Email Suffix enterprise.defaults.email.suffix	bea.com Suffix added to a username to determine their default email address
Allow Distribution List Email cmee.email.cc	<input checked="" type="radio"/> True <input type="radio"/> False Allow users to create distribution lists so that the members of the list are automatically copied on certain email notifications that are sent as part of the asset registration process.
Allow External Emails in a Distribution List cmee.email.nonuser.cc	<input checked="" type="radio"/> True <input type="radio"/> False Allow users to provide external email addresses in their distribution lists for email notifications.
SMTP Server cmee.server.smtp	amazon.fastline.com The IP address of the SMTP server used for auto-generated email messages.
Use External Email System cmee.server.smtp.send-with-cron	<input type="radio"/> True <input checked="" type="radio"/> False True = Uses external email system for notifications. False = Uses ALER internal email "send" mechanism for notifications. NOTE - Restart server after changing this setting.
Send Email Interval cmee.server.smtp.send-interval	1 In minutes, the send interval between automatic email messages
Send System Email as HTML cmee.server.smtp.send.formashtml	<input type="radio"/> True <input checked="" type="radio"/> False Enables the ability to send email in HTML format
Send System Email with Reply-To Header cmee.server.smtp.send.replytorequired	<input type="radio"/> True <input checked="" type="radio"/> False Sets form letters to be sent with optional Reply-To header set to From address.
Notification Email Delimiter cmee.email.delimiter	- The delimiter used for sending notification emails to multiple email addresses based on the default email client (Outlook would use semi-colon. Express a comma).
Send Diagnostic Email to BEA cmee.server.smtp.senddiag	<input checked="" type="radio"/> True <input type="radio"/> False Enables monthly diagnostic email to be sent to BEA for informational purposes.

- **Allow Distribution List Email**
 - `cmee.email.cc`
 - The **True** and **False** radio buttons toggle the availability of the email distribution list feature. This allows users to create distribution lists so that the list members are automatically copied on certain email notifications that are sent as part of the asset registration process.
- **Allow External Emails in a Distribution List**
 - `cmee.email.nonuser.cc`
 - The **True** and **False** radio buttons determine the ability for a user to specify external email addresses in distribution lists. **True** allows external email addresses in distribution lists. **False** restricts distribution lists to only internal ALER users.
- **SMTP Server**
 - `cmee.server.smtp`
 - The IP address of the SMTP server used for auto-generated email messages.
- **Use External Email**
 - `cmee.server.smtp.send-with-cron`
 - **True** and **False** radio buttons determine the selection of the email mechanisms for automated ALER messages. **True** enables the external mechanism. **False** enables ALER's internal email send mechanism.

Note: Changes to this setting require server restart.
- **Send Email Interval**
 - `cmee.server.smtp.send-interval`
 - This setting determines the number of minutes between automatic ALER email messages.

- **Send System Email as HTML**

- `cmee.server.smtp.send.format-html`
- The **True** and **False** radio buttons toggle the selection of HTML or plain-text formatting of automatic ALER messages.

True enables HTML formatting.

False enables plain text formatting.

- **Send System Email with Reply-To Header**

- `cmee.server.smtp.send.replyto-required`
- The **True** and **False** radio buttons toggle the option to include a Reply-to header in automated ALER messages. The Reply-to header includes the From address.

True enables the Reply-to header.

- **Notification Email Delimiter**

- `cmee.email.delimiter`
- Use the drop-down menu to select the appropriate delimiter (comma or semi-colon) for multiple email addresses as determined by the default email client. (For example, Microsoft Outlook uses the semi-colon, while Outlook Express uses the comma).

- **Send Diagnostic Email to BEA**

- `cmee.server.smtp.senddiag`
- The **True** and **False** radio buttons toggle an automatic monthly diagnostic email to BEA, for internal informational purposes only.

- **Default Email Suffix**

- `enterprise.defaults.email.suffix`
- The information supplied in this text box will be automatically suffixed to usernames to form the default user email address.

Server Settings: Upload Area

Upload Area	
Submission Upload Directory cmee.server.paths.upload	<input type="text"/> The directory used to store files uploaded during asset submission. If left blank, users will not be able to upload files. (This will not affect their ability to link to files).
Registrar Submission Upload Path cmee.server.paths.upload-registrar	<input type="text"/> The path for Asset Editor browsing. Usually a UNC path which allows direct access to the submission upload directory.
Submission Upload Artifact Store cmee.server.paths.upload-repository	None <input type="button" value="v"/> Artifact store which allows direct public access to the submitted files. Used for one-step acceptance of submitted files in the Asset Editor.

- **Submission Upload Directory**

- cmee.server.paths.upload
- Defines a locally referenced operating system path to upload files onto the application server directly via an HTTP file upload process. This property enables the following features:
 - Enables the **Add Attachment Now** option in the **Asset Submission** form. (Required if files are to be attached to assets during the submission process.)
 - Enables **Uploaded Submission Files** option in the **Asset Editor**.

- **Registrar Submission Upload Path**

- cmee.server.paths.upload-registrar
- Enables file browsing through the **Asset Editor** (Optional).
 - The path, when hosted by UNC, requires Windows OS or Samba/Sharity.
 - Enables the appearance of the **Browse** button in **Uploaded Submission Files** in the **Asset Editor**.

- **Submission Upload Artifact Store**

- cmee.server.paths.upload-repository
- Sets a configured artifact store to allow direct public access to the submitted files. Used for one-step acceptance of submitted files in the Asset Editor. When this property is set:
 - Asset files that available for use/download are visible.
 - The **Accept** button is visible in the uploaded submission files section of the **Asset Editor**.

Proxy Downloads

ALER includes an additional option that allows the Repository application server to act as a repository proxy for the user. This feature automatically removes username and password text that is supplied in the HTTP URL during file downloads. This feature is applicable to any artifact store providing that ALER can have network connectivity to resources in that store. Contact ALER support for details.

Examples of Artifact Store Configurations

For instructions on configuring one of the following artifact stores, see the ALER "Configuration Guide."

- **UNC**

- *Hostname:* aler
- *Path:* upload/
- *Username:* aler
- *Password:* flash
- *URL:* file:///aler/upload/

- **HTTP**

- *Hostname:* aler
- *Path:* aler-web/upload
- *Username:* aler
- *Password:* flash
- *URL:* http://aler:flash@aler/aler-web/upload/

- **FTP**

- *Hostname:* meta.aler.com
- *Path:* upload
- *Username:* aler
- *Password:* flash
- *URL:* ftp://aler:flash@meta.aler.com/upload/

- **ClearCase**

- *Hostname:* clearcase.aler.com
- *Path:* ccaseweb/bin/ccweb
- *Username:* aler
- *Password:* flash
- *URL:* http://clearcase.aler.com/ccaseweb/bin/ccweb/?dir=/&elem=&cmd=view&user=aler&password=flash

- **PVCS**

- *Hostname:* pvcs.aler.com
- *Path:* dav
- *Username:* aler
- *Password:* flash
- *URL:* http://aler:flash@pvcs.aler.com/dav/

- **Raw URI**

- *Name:* Example RAW URI
- *RAW URI:* http://www.example.com/path1/path2?parameter1¶meter2
- *URL:* http://www.example.com/path1/path2?parameter1¶meter2

Server Settings: Caching

Caching

Preload Asset Cache at Start-up
`cmee.assets.preload.at-startup` True False
Preloads the Asset cache upon starting the application server.

Preload Asset Cache as Seperate Thread
`cmee.assets.preload.as-seperate-thread` True False
When preloading the Asset cache, spawn it as a seperate thread.

- **Preload Asset Cache at Start-up**

- `cmee.assets.preload.at-startup`
- Select the **True** radio button to preload the asset cache on application server start-up.

True preloads the asset cache.


- **Preload Asset Cache as Seperate Thread**

- `cmee.assets.preload.as-seperate-thread`
- Select the **True** radio button to spawn the preloaded asset cache as a separate thread on application server startup.

Enterprise Authentication: General

General	
Unapproved User Login enterprise.security.unapproveduser.allowlogin	<input checked="" type="radio"/> True <input type="radio"/> False Enables unapproved users to log in to the system. This is useful for LDAP or container-managed authentication.
Display Login Pop-up enterprise.security.showloginpopup	<input checked="" type="radio"/> True <input type="radio"/> False Enables the display of a pop-up box at login for all users.
Maximum Failed Login Attempts enterprise.security.loginattempt.max	<input type="text" value="5"/> The maximum number of failed login attempts permitted before locking out a user. Lockouts are disabled if this value is less than or equal to zero.
Concurrent Logins Per User enterprise.security.concurrentuser.max	<input type="text" value="1"/> The maximum number of concurrent logins each user is permitted. A value of less than or equal to zero permits infinite concurrent user logins.
Grace Logins enterprise.security.password.expiration.gracelogins	<input type="text" value="10"/> Number of times user is allowed to log in after their password has expired.
Enable LDAP Login enterprise.authentication.ldap.enabled	<input checked="" type="radio"/> True <input type="radio"/> False Enables the LDAP Login Module for authentication.
Enable Container Login enterprise.authentication.container.enabled	<input checked="" type="radio"/> True <input type="radio"/> False Enables the Container Login Module for authentication.
Synch container roles enterprise.authentication.container.synchroles.enabled	<input type="radio"/> True <input checked="" type="radio"/> False Enables the synchronizing of container roles.
Enable Advanced Container Login enterprise.authentication.advancedcontainer.enabled	<input checked="" type="radio"/> True <input type="radio"/> False Enables the Advanced Container Login Module for authentication.
New Unapproved User Notification cmee.new.unapproved.users.notify	<input checked="" type="radio"/> True <input type="radio"/> False Send email to the security admin when a new user is created via external authentication such as LDAP or container.

- **Unapproved User Login**
 - enterprise.security.unapproveduser.allowlogin
 - The **True** and **False** radio buttons toggle the ability for unapproved users to log in to the system. This is useful when using LDAP or container-managed authentication.
- **Display Login Pop-up**
 - enterprise.security.showloginpopup
 - The **True** and **False** radio buttons toggle the default display of the ALER login pop-up. The pop-up identifies the users and displays login information.



- **Maximum Failed Login Attempts**
 - enterprise.security.loginattempt.max
 - The numerical entry in the text box determines the number of failed login attempts before user lock-out. A value of zero or less disables lock-out.



- **Concurrent Logins Per User**
 - `enterprise.security.concurrentuser.max`
 - The numerical value entered in the text box determines the maximum number of concurrent logins each user is permitted. A value of less than or equal to zero permits infinite concurrent user logins.
- **Grace Logins**
 - `enterprise.security.password.expiration.gracelogins`
 - The numerical value entered in the text box determines the number of times a user is allowed to log in after his/her password has expired.
- **Enable LDAP Login**
 - `enterprise.authentication.ldap.enabled`
 - Enables the LDAP Login Module for authentication.
- **Enable Container Login**
 - `enterprise.authentication.container.enabled`
 - Enables the Container Login Module for authentication.
- **Enable Advanced Container Login**
 - `enterprise.authentication.advancedcontainer.enabled`
 - Select the **True** radio button to enable the Advanced Container Login Module for authentication.
- **Synchronize Container Roles**
 - `enterprise.authentication.container.synchroles.enabled`
 - Enables the synchronization of existing Java EE container roles.
- **Enable Advanced Container Login**
 - `enterprise.authentication.advancedcontainer.enabled`
 - Enables the Advanced Container Login Module for authentication.
- **Default Email Suffix**
 - `enterprise.defaults.email.suffix`
 - Suffix added to a username to determine their default email address.
- **New Unapproved User Notification**
 - `cmee.new.unapproved.users.notify`
 - The **True** and **False** radio buttons toggle the feature that automatically sends an email to the security administrator when a new user is created via external authentication, such as LDAP or a Java EE container.

Enterprise Authentication: Authentication Token


Authentication Token	
Authentication Token Expiration <code>enterprise.defaults.authtokens.expiration.value</code>	<input type="text" value="12"/> Sets the time until an authentication token expires, and is eligible to be purged
Authentication Token Expiration Units <code>enterprise.defaults.authtokens.expiration.period</code>	hours ▾ Sets the time units used for determining authentication token expiration
Authentication Token Purge Expired Frequency <code>enterprise.defaults.authtokens.purgefrequency.value</code>	<input type="text" value="1"/> Sets the amount of time between purges of expired authentication tokens
Authentication Token Purge Expired Frequency Units <code>enterprise.defaults.authtokens.purgefrequency.period</code>	hours ▾ Sets the time units used to determine the authentication token purge expired frequency

- **Authentication Token Expiration**

- `enterprise.defaults.authtokens.expiration.value`
- The numerical value entered in the text box determines the period of time (in units determined by the **Authentication Token Expiration Units** menu selection) until an authentication token expires and is eligible to be purged.

- **Authentication Token Expiration Units**

- `enterprise.defaults.authtokens.expiration.period`
- Use the drop-down menu to select the units of time to be used in conjunction with the **Authentication Token Expiration** setting.



- **Authentication Token Purge Expired Frequency**

- `enterprise.defaults.authtokens.purgefrequency.value`
- The numerical value entered in the text box determines the period of time (in units determined by the **Authentication Token Purge Expired Frequency Units** menu selection) between purges of expired authentication tokens.

- **Authentication Token Purge Expired Frequency Units**

- `enterprise.defaults.authtokens.purgefrequency.period`
- Use the drop-down menu to select the units of time to be used in conjunction with the **Authentication Token Purge Expired Frequency** setting.

Enterprise Authentication: Password Settings

Password Settings	
Password - Minimum Length enterprise.security.password.composition.minimumlength	<input type="text" value="4"/> The minimum number of characters required for a valid user password. Note that administrators setting a password are not affected by this.
Password - Alpha Character Required enterprise.security.password.composition.require.alpha	<input checked="" type="radio"/> True <input type="radio"/> False Requires passwords to contain at least one alpha character. Note that administrators setting a password are not affected by this.
Password - Numeric Character Required enterprise.security.password.composition.require.numeric	<input type="radio"/> True <input checked="" type="radio"/> False Requires passwords to contain at least one numeric character. Note that administrators setting a password are not affected by this.
Password - Special Character Required enterprise.security.password.composition.require.special	<input type="radio"/> True <input checked="" type="radio"/> False Requires passwords to contain at least one special character. Note that administrators setting a password are not affected by this.
Password Expiration enterprise.security.password.expiration.days	<input type="text" value="90"/> Number of days until password expires. Password expiration is disabled if this value is less than or equal to zero.
Password History Tracking enterprise.security.password.history.count	<input type="text" value="5"/> Number of prior passwords remembered by the system. This list is used to prevent the reuse of passwords.
Password History - Minimum Tracking Age enterprise.security.password.history.managehours	<input type="text" value="24"/> Sets the minimum number of hours a password must be in effect before it is eligible to be added to the password history. This is useful to prevent circumvention of the password history by repeatedly changing passwords.

- **Password - Minimum Length**
 - enterprise.security.password.composition.minimumlength
 - The numerical value entered in the text box determines the minimum number of characters required for a valid password.
 - **Note:** This setting does not apply to passwords created by individuals in the **Admin** role.
- **Password - Alpha Character Required**
 - enterprise.security.password.composition.require.alpha
 - Select the **True** radio button to set the requirement that passwords contain at least one alphabetic character.
 - **Note:** This setting does not apply to passwords created by individuals in the **Admin** role.
- **Password - Numeric Character Required**
 - enterprise.security.password.composition.require.numeric
 - Select the **True** radio button to set the requirement that passwords contain at least one one numeric character.
 - **Note:** This setting does not apply to passwords created by individuals in the **Admin** role.
- **Password - Special Character Required**
 - enterprise.security.password.composition.require.special
 - Select the **True** radio button to set the requirement that passwords contain at least one special character.
 - **Note:** This setting does not apply to passwords created by individuals in the **Admin** role.
- **Password Expiration**
 - enterprise.security.password.expiration.days

- The numerical value entered in the text box determines the number of days until password expiration.

A value of zero or less disables password expiration.

- **Password History Tracking**

- `enterprise.security.password.history.count`
- The numerical value entered in the text box determines the number of prior passwords remembered by the system. The password history is used to prevent the reuse of passwords.

- **Password History - Minimum Tracking Age**

- `enterprise.security.password.history.minagehours`
- The numerical value entered in the text box determines the minimum number of hours a password must be in effect before it is added to the password history. This feature is useful for preventing circumvention of the password history by repeatedly changing passwords.

Enterprise Authentication: Plugin Login Settings

Property	Value	Description
Plug-in Login Module Class Name <code>enterprise.loginmodules.pluggableloginmodule.classname.</code>	<code>com.fishline...</code>	Class name of the plug-in login module
Plug-in Login Module Display Name <code>enterprise.loginmodules.pluggableloginmodule.displayname.</code>	<code>Enterprise Dev</code>	Display name of the plug-in login module
Plug-in Login Module <code>enterprise.loginmodules.pluggableloginmodule.enabled.</code>	<code>true</code>	Enables the plug-in login module
Plug-in Login Module - Internal Checking <code>enterprise.loginmodules.pluggableloginmodule.internalchecking.</code>	<code>true</code>	Enables internal checking of password expiration and grace logins for the plug-in login module. LDAP-based and other external login modules should always pass a false in this parameter since we will defer these types of checks to the external authentication system.

- **Plug-in Login Module Class Name**

- `enterprise.loginmodules.pluggableloginmodule.classname`
- Text entered in the text box identifies the class name for the plug-in login module.

Click **+Add** as necessary to add class names for additional plug-in login modules.

- **Plug-in Login Module Display Name**

- `enterprise.loginmodules.pluggableloginmodule.displayname`
- Text entered in the text box appears as the display name of the plug-in login module.

Click **+Add** as necessary to add display names for additional plug-in modules.

- **Plug-in Login Module**

- `enterprise.loginmodules.pluggableloginmodule.enabled`
- Enter **true** in the text box to enable the plug-in login module.

Click **+Add** as necessary to add and enable/disable additional plug-in modules.

- **Plug-in Login Module - Internal Checking**

- `enterprise.loginmodules.pluggableloginmodule.internalchecking`
- Enter **true** in the text box to enable internal checking of password expiration and grace logins for the configured plug-in login module.

Enter **false** in the text box when using LDAP-based, SSO-based, Container Managed or other external login modules to defer these types of checks to the external authentication system.

Click **+Add** as necessary to add and enable/disable internal checking for additional plug-in modules.

Enterprise Authentication: Container Login Settings

Container Login Settings	
Container Login Module Class Name enterprise.loginmodules.containerloginmodule.classname	<input type="text" value="com.fishline.enterprise.authentication.server.loginmodule.Container"/> Class name of the container login module
Container Login Module Display Name enterprise.loginmodules.containerloginmodule.displayname	<input type="text" value="Enterprise Container Login"/> Display name of the container login module
Container Login Module enterprise.loginmodules.containerloginmodule.enabled	<input type="radio"/> True <input checked="" type="radio"/> False Enables the container login module
Container Login Module - Internal Checking enterprise.loginmodules.containerloginmodule.internalchecking	<input type="radio"/> True <input checked="" type="radio"/> False Enables internal checking for the container login module

- **Container Login Module Class Name**
 - `enterprise.loginmodules.containerloginmodule.classname`
 - Text entered in the text box identifies the class name of the container login module.
- **Container Login Module Display Name**
 - `enterprise.loginmodules.containerloginmodule.displayname`
 - Text entered in the text box appears as the display name of the container login module.
- **Container Login Module**
 - `enterprise.loginmodules.containerloginmodule.enabled`
 - Select the **True** radio button to enable the container login module.
- **Container Login Module - Internal Checking**
 - `enterprise.loginmodules.containerloginmodule.internalchecking`
 - Select the **True** radio button to enable internal checking for the container login module.

Enterprise Authentication: Cookie Login Settings

Cookie Login Settings	
Allow Cookie Login enterprise.security.cookielogin.allow	<input checked="" type="radio"/> True <input type="radio"/> False Enables automatic login using a cookie. If this is not enabled, manual login is required.
Default to Cookie Login enterprise.security.cookielogin.default	<input checked="" type="radio"/> True <input type="radio"/> False Enables automatic login checkbox on Login screen to be checked by default for all users.
Cookie Login Module Class Name enterprise.loginmodules.cookieloginmodule.classname	<input type="text" value="com.flashline.enterprise.authentication.server.loginmodule.CookieLogin"/> Class name of the cookie login module
Cookie Login Module Display Name enterprise.loginmodules.cookieloginmodule.displayname	<input type="text" value="Enterprise Cookie Login"/> Display name of the cookie login module
Cookie Login Module enterprise.loginmodules.cookieloginmodule.enabled	<input checked="" type="radio"/> True <input type="radio"/> False Enables the cookie login module
Cookie Login Module - Internal Checking enterprise.loginmodules.cookieloginmodule.internalchecking	<input checked="" type="radio"/> True <input type="radio"/> False Enables internal checking for the cookie login module

- **Allow Cookie Login**
 - enterprise.security.cookielogin.allow
 - Select the **True** radio button to enable automatic login using a cookie. If disabled, manual login is required.
- **Default to Cookie Login**
 - enterprise.security.cookielogin.default
 - Select the **True** radio button to set **Enable automatic login** as the default in the ALER login pop-up.

Please Login

Username:

Password:

Enable automatic login

- **Cookie Login Module Class Name**
 - enterprise.loginmodules.cookieloginmodule.classname
 - Text entered in the text box identifies the class name of the cookie login module.
- **Cookie Login Module Display Name**
 - enterprise.loginmodules.cookieloginmodule.displayname
 - Text entered in the text box appears as the display name of the cookie login module.
- **Cookie Login Module**
 - enterprise.loginmodules.cookieloginmodule.enabled
 - Select the **True** radio button to enable the cookie login module.
- **Cookie Login Module - Internal Checking**
 - enterprise.loginmodules.cookieloginmodule.internalchecking
 - Select the **True** radio button to enable internal checking for the cookie login module.

External Integrations: UDDI

UDDI	
UDDI - Default Business <small>cmees.uddi.default.business</small>	Select default business name here <input type="text"/> Default UDDI Business Entity. This will be assigned to any UDDI services that do not have a business.
Default UDDI User Name <small>cmees.uddi.user</small>	<input type="text" value="topline"/> Default UDDI user name, to be used for UDDI searches when no user has been supplied.
Default UDDI Password <small>cmees.uddi.user.password</small>	<input type="text"/> The password for the default UDDI user.
Business Service Relationship Name <small>cmees.uddi.business.service.relationship</small>	Provided by Business Entity <input type="text"/> Name of the relationship that links UDDI Business Services to UDDI Business Entities. (Requires App Server restart before changes take affect)
UDDI <small>cmees.uddi.server.enabled</small>	<input checked="" type="radio"/> True <input type="radio"/> False Enables repository to act as a UDDI registry for select apps.
UDDI - Suppress Instance Details <small>cmees.uddi.server.suppress.instdet</small>	<input checked="" type="radio"/> True <input type="radio"/> False Some UDDI clients cannot properly process the InstanceDetails element in a bindingTemplate response. This setting controls whether that element is returned as part of the response to a get_serviceDetail request to the builtin UDDI server.
UDDI - AccessPoint Mapping <small>cmees.uddi.server.accesspoint.mapping</small>	<input type="text" value="/access-port"/> For AssetTypes that are exposed through UDDI as services, this property allows the specification of an element in the AssetType to be used for the access point of the service in the UDDI model.
UDDI - AccessPointType Mapping <small>cmees.uddi.server.accesspointtype.mapping</small>	<input type="text" value="/access-port-type"/> For AssetTypes that are exposed through UDDI as services, this property allows the specification of an element in the AssetType to be used for the protocol type of the access point of the service in the UDDI model.
UDDI - WSDL Location Mapping <small>cmees.uddi.server.wsdl.mapping</small>	<input type="text"/> For AssetTypes that are exposed through UDDI as services, this property allows the specification of an element in the AssetType to be used for the location of the WSDL. If this value is left undefined, then the system will inspect the associated files on each Asset, in an attempt to discover WSDL that has been specified as a payload of the asset.
Import - Enable UDDI Import <small>cmees.import.uddi.enabled</small>	<input checked="" type="radio"/> True <input type="radio"/> False Enables functionality to import assets from an external UDDI registry.
Import - Default UDDI Service Type <small>cmees.import.uddi.service.assettype</small>	Service <input type="text"/> Specifies the name of the default AssetType to which UDDI services will be imported.

- UDDI
 - `cmees.uddi.enabled`
 - Enables the UDDI Web Service Plugin.
- UDDI - Default Business
 - `cmees.uddi.default.business`
 - Use the drop-down menu to select the default business entity to be assigned to any UDDI services to which no business has been assigned.
- Default UDDI User Name
 - `cmees.uddi.user`
 - The text entered in the text box provides the default user name for UDDI searches when no user has been supplied.
- Business Service Relationship Name
 - `cmees.uddi.business.service.relationship`
 - Use the drop-down menu to select the relationship that will link UDDI Business Services to UDDI Business Entities.

Note: Changes to this setting will take effect after appserver restart.
- UDDI
 - `cmees.uddi.server.enabled`
 - Select the **True** radio button to allow ALER to act as a UDDI registry for selected applications.

- **UDDI - Suppress Instance Details**

- `cmee.uddi.server.suppress.instdet`
- Some UDDI clients cannot properly process the `instanceDetails` element in a `bindingTemplate` response. Select the **True** radio button to suppress the `instanceDetails` element in the response to a `get_serviceDetail` request to the built-in UDDI server.

- **UDDI - AccessPoint Mapping**

- `cmee.uddi.server.accesspoint.mapping`
- For asset types that are exposed through UDDI as services, this property specifies the asset type element that is to be used for the access point of the service in the UDDI model.

- **UDDI - AccessPointType Mapping**

- `cmee.uddi.server.accesspointtype.mapping`
- For asset types that are exposed through UDDI as services, this property specifies the asset type element that is to be used for for the protocol type of the access point of the service in the UDDI model.

- **UDDI - WSDL Location Mapping**

- `cmee.uddi.server.wsdl.mapping`
- For asset types that are exposed through UDDI as services, this property specifies the asset type element that is to be used for for the location ocation of the WSDL.

If this value is left undefined, the system will inspect each relevant asset's associated files in an attempt to discover WSDL that has been specified as part of the asset payload.

- **Import - Enable UDDI Import**

- `cmee.import.uddi.enabled`
- Select the **True** radio button to display **Import from UDDI** link in the **Import Export** section in the **Admin** sidebar. This setting allows the import of assets from an external UDDI registry.

- **Import - Default UDDI Service Type**

- `cmee.import.uddi.service.assettype`
- Use the drop-down menu to specify the default asset type to be assigned to imported UDDI services.

External Integrations: Eventing

Eventing	
Enable Event Manager cme.e.eventframework.enabled	<input type="radio"/> True <input checked="" type="radio"/> False Enables the Advanced Registration Flow subsystem.
Event Manager Notifier Thread Sleep (seconds) cme.e.eventframework.notifier.sleep	60 Specifies in seconds how long the notifier should wait, if an endpoint is unavailable, before retrying to send an event.
Event Manager Store Thread Sleep (seconds) cme.e.eventframework.store.sleep	15 Specifies in seconds how long the Event Manager's Store Manager thread should sleep before polling for the next available batch of event stored in memory.
Event Manager Delivery Thread Sleep (seconds) cme.e.eventframework.delivery.sleep	13 Specifies in seconds how long the Event Manager's Delivery Manager thread should sleep before selecting the next available event from the JMS server.
Event Manager Embedded JMS Enable cme.e.eventframework.embedded.jms.enabled	<input checked="" type="radio"/> True <input type="radio"/> False Select the False radio button to disable the Event Manager's Embedded ActiveMQ JMS. Disabling this property will force the Event Manager to use an external JMS server. If this setting is disabled, all the JNDI properties should be configured.
JNDI URL cme.e.eventframework.jndi.provider.url	ts://localhost:7001 Sets the JNDI URL.
JNDI User name cme.e.eventframework.jndi.user	 Sets the JNDI User name.
JNDI Password cme.e.eventframework.jndi.password	 Sets the JNDI Password.
JNDI Context Factory cme.e.eventframework.jndi.context.factory	weblogic.jndi.wlInitialContextFactory Sets JNDI Context Factory.
JMS Connection Factory cme.e.eventframework.jms.connection.factory	weblogic.examples.jms.TopicConnectionFactory Specifies the JMS connection factory to enable JMS clients to create JMS connections.
JMS Topic cme.e.eventframework.jms.topic	weblogic.examples.jms.exampleTopic Specifies the JMS topic, which is a pub/sub destination type for a JMS server.
JMS Subscribers Client ID cme.e.eventframework.jms.subscribers.client.id	ALERJmsSubscriber Sets JMS Subscribers Client ID. The purpose of the client identifier is to associate a connection and its objects with a state maintained on behalf of the client by a provider. By definition, the client state identified by a client identifier can be in use by only one client at a time.
JMS Producers Client ID cme.e.eventframework.jms.producers.client.id	ALERJmsProducer Sets JMS Producers Client ID. The purpose of the client identifier is to associate a connection and its objects with a state maintained on behalf of the client by a provider. By definition, the client state identified by a client identifier can be in use by only one client at a time.
Event Manager JMS Subscribers Enable cme.e.eventframework.jms.subscribers.enabled	<input checked="" type="radio"/> True <input type="radio"/> False If set to False, then the internal JMS subscribers will not be enabled. This is to make sure that the embedded JMS server is started. However, an external tool can be used to connect to the embedded JMS server using the specified JMS Durable Subscriber name. Once connected, this tool can also be used to clean up events stored by the Event Manager.
JMS Delivery Mode cme.e.eventframework.jms.deliverymode	PERSISTENT Specifies the JMS delivery mode of PERSISTENT or NON-PERSISTENT. Although more reliable, persisting events to a store can affect performance.
JMS Message Expiration cme.e.eventframework.jms.expiration	0 Specifies the message expiration. If set, unprocessed events will expire in the specified number of seconds.
Lazy Initialize Event Manager cme.e.eventframework.lazy.load	<input type="radio"/> True <input checked="" type="radio"/> False Select the True radio button to "lazily" initialize the Event Manager only when an event is produced for the first time.

- **Enable Event Manager**
 - cme.e.eventframework.enabled
 - Select the **True** radio button to enable the Advanced Registration Flow subsystem.
- **Event Manager Notifier Thread Sleep (seconds)**
 - cme.e.eventframework.notifier.sleep
 - Specifies in seconds how long the notifier should wait, if an endpoint is unavailable, before retrying to send an event.
- **Event Manager Store Thread Sleep (seconds)**
 - cme.e.eventframework.store.sleep
 - Specifies in seconds how long the Event Manager's Store Manager thread should sleep before polling for the next available event stored in memory.
- **Event Manager Delivery Thread Sleep (seconds)**
 - cme.e.eventframework.delivery.sleep
 - Specifies in seconds how long the Event Manager's Delivery Manager thread should sleep before selecting the next available event from the JMS server.
- **Event Manager Embedded JMS Enable**
 - cme.e.eventframework.embedded.jms.enabled
 - Select the **False** radio button to disable the Event Manager's Embedded ActiveMQ JMS. Disabling this property will force the Event Manager to use an external JMS server. If this setting is disabled, all the JNDI properties should be configured.
- **JNDI URL**
 - cme.e.eventframework.jndi.provider.url
 - Specifies the JNDI URL.
- **JNDI User Name**
 - cme.e.eventframework.jndi.user
 - Specifies the JNDI user name.
- **JNDI Password**
 - cme.e.eventframework.jndi.password

- Specifies the JNDI password.
- **JNDI Context Factory**
 - `cmee.eventframework.jndi.context.factory`
 - Specifies the JNDI context factory.
- **JMS Connection Factory**
 - `cmee.eventframework.jms.connection.factory`
 - Specifies the JMS connection factory to enable JMS clients to create JMS connections.
- **JMS Topic**
 - `cmee.eventframework.jms.topic`
 - Specifies the JMS topic, which is a pub/sub destination type for a JMS server.
- **JMS Subscribers Client ID**
 - `cmee.eventframework.jms.subscribers.client.id`
 - Specifies the JMS subscriber's client ID. The purpose of the subscriber client identifier is to associate a connection and its objects with a state maintained on behalf of the client by a provider. By definition, the client state identified by a client identifier can be in use by only one client at a time.
- **JMS Producers Client ID**
 - `cmee.eventframework.jms.producers.client.id`
 - Specifies the JMS producer's client ID. The purpose of the producer client identifier is to associate a connection and its objects with a state maintained on behalf of the client by a provider. By definition, the client state identified by a client identifier can be in use by only one client at a time.
- **Event Manager JMS Subscribers Enabled**
 - `cmee.eventframework.jms.subscribers.enable`
 - If set the **False** radio button is selected, then the internal JMS subscribers will not be enabled. This is to make sure that the embedded JMS server is started. However, an external JMS tool can be used to connect to the embedded JMS server using the specified JMS Subscriber Client ID name. Once connected, the external tool can also be used to clean up events stored by the Event Manager.
- **JMS Delivery Mode**
 - `cmee.eventframework.jms.deliverymode`
 - Specifies the JMS delivery mode of PERSISTENT or NON-PERSISTENT. Although more reliable, persisting events to a store can affect performance.
- **JMS Message Expiration**
 - `cmee.eventframework.jms.expiration`
 - Specifies the message expiration time in seconds. If set, unprocessed events will expire in the specified number of seconds. The default value of 0 means that messages will never expire.
- **Lazy Initialize Event Manager**
 - `cmee.eventframework.lazy.load`
 - Select the **True** radio button to "lazily" initialize the Event Manager only when an event is produced for the first time.

Import / Export and Introspection: Import/Export Client

Import / Export	
Submission Logging of Integrated Endpoint cme.tooling.submission.logging	<input type="radio"/> True <input checked="" type="radio"/> False Enables logging of import / export jobs controlling asset submissions through integrations with external endpoints.
Asset Submission from Integrated Endpoint cme.tooling.submission.enabled	<input checked="" type="radio"/> True <input type="radio"/> False Enables asset submissions generated through integrations with external endpoints.
Import/Export Client cme.importexport.enabled	<input checked="" type="radio"/> True <input type="radio"/> False Enables the Import/Export client.

- **Submission Logging of Integrated Endpoint**
 - cme.tooling.submission.enabled
 - Enables logging of import/export jobs controlling asset submissions through integrations with external endpoints.
- **Asset Submission from Integrated Endpoint**
 - cme.tooling.submission.enabled
 - Enables asset submissions generated through integrations with external endpoints.
- **Import/Export Client**
 - cme.importexport.enabled
 - The **True** and **False** radio buttons toggle the Import/Export client.

True displays the **Import / Export** section in the sidebar on the **Admin** screen.




Import / Export and Introspection: WSDL and XSD

WSDL and XSD	
Import - Enable WSDL Import cmee.import.wsdl.enabled	<input checked="" type="radio"/> True <input type="radio"/> False Enables the import process that introspects WSDL files to automatically populate service and schema asset metadata and their relationships.
Import - Default WSDL Service Type cmee.import.wsdl.service.assettype	Service Specifies the name of the default AssetType to which WSDL services will be imported.
Import - Default XML Schema Type cmee.import.wsdl.xsd.assettype	XML Schema Specifies the name of the default AssetType to which XML Schemas will be imported when importing WSDL and/or a UDDI registry.
Import - Default DTD Type cmee.import.wsdl.dtd.assettype	 Specifies the name of the default AssetType to which DTDs will be imported when importing WSDL and/or a UDDI registry.
Import - Relationship for imports cmee.import.wsdl.relationship.imports	References Specifies the Relationship for imports found during WSDL introspection.
Import - Relationship for same WSDL services cmee.import.wsdl.relationship.same-wsdl	Related to Specifies the Relationship between multiple services found during the same WSDL introspection.
Enable WSDL Introspection Element cmee.wsdl-introspection.enabled	<input checked="" type="radio"/> True <input type="radio"/> False Enables an asset detail plugin element that introspects WSDL files to automatically populate the web service asset metadata.

- **Import - Enable WSDL import**
 - `cmee.import.wsdl.enabled`
 - Select **True** to display the **Import from WSDL** link in the **Import Export** section in the **Admin** sidebar and to enable the import process that introspects WSDL files to automatically populate service and schema asset metadata and their relationships.




- **Import - Default WSDL Service Type**
 - `cmee.import.wsdl.service.assettype`
 - Use the drop-down menu to select the default asset type to which WSDL services will be imported.




- **Import - Default XML Schema Type**

- `cmee.import.wsdl.xsd.assettype`
- Use the drop-down menu to select the default asset type to which XML Schemas will be imported when importing WSDL and/or a UDDI registry.




- **Import - Default DTD Type**


- `cmee.import.wsdl.dtd.assettype`
- Use the -drop-down menu to select the default asset type to which DTDs will be imported when importing WSDL and/or a UDDI registry.



- **Import - Relationship for imports**
 - `cmee.import.wsdl.relationship.imports`
 - Use the drop-down menu to select the default relationship to be assigned to artifacts imported during WSDL introspection.




- **Import - Relationship for same WSDL services**
 - `cmee.import.wsdl.relationship.same-wsdl`
 - Specifies the Relationship between multiple services found during the same WSDL introspection.



- **WSDL Introspection Element**

- `cmee.wsd1-introspection.enabled`
- Select **True** to add the **WSDL Introspection** element to the list of elements available in the **Type Manager**.



BPEL

- **Import - Enable BPEL import**
 - `cmee.import.bpel.enabled`
 - Select **True** to display the **Import from BPEL** link in the **Import Export** section in the **Admin** sidebar and to enables the import process that introspects BPEL files to automatically create assets from them.

Email Templates

Overview

Certain specific events within AquaLogic Enterprise Repository trigger automated email responses. For instance, when a new asset is submitted, an email notification is sent to the registrar. The various templates are described below.

- **Name:** All Asset Tabs Approved
- **Description:** Notifies user assigned to asset and Registrar that all tabs have been approved.
- **From:** User logged in that approves tab
- **To:** Registrar email address, User(s) that is/are assigned to asset
- **Content:** "The final tab, <%asset.tab%>, for the asset <%asset.name%> has been approved. All tabs are now approved."

- **Name:** Asset Accepted
- **Description:** Notifies the submitter that the asset has been accepted.
- **From:** User logged in that submits asset
- **To:** User logged in that submits asset
- **Content:** "The asset <%asset.name%> has been accepted."

- **Name:** Asset Active
- **Description:** Notifies submitter/subscriber(s) that asset has been marked active.
- **From:** User updating the asset to Active
- **To:** User logged in that submits asset
- **Content:** "The asset <%asset.name%> has been marked active."

- **Name:** Asset Assign
- **Description:** Notifies user when assigned to asset.
- **From:** Registrar user
- **To:** User logged in that submits asset
- **Content:** "You have been assigned to the asset <%asset.name%>."

- **Name:** Asset Deletion
- **Description:** Notifies submitter/subscriber(s) that an asset has been deleted.
- **From:** User updating the asset to Deleted
- **To:** User logged in that submits asset
- **Content:** "The asset <%asset.name%> has been deleted."

- **Name:** **Asset Editor** Submission
- **Description:** Notifies registrar that a new asset has been submitted through the **Asset Editor**.
- **From:** User submitting asset through the **Asset Editor**
- **To:** Registrar email address that submitted asset
- **Content:** "<%user.name%> submitted the Asset <%asset.name%> using the **Asset Editor**."

- **Name:** Asset Has Been Expired

- **Description:** Notifies the registrar and the users assigned to the asset that it has been expired.
 - **From:** Registrar email address
 - **To:** Registrar and users who are assigned to an asset
 - **Content:** "The asset, <%asset.name%> (<%asset.version%>) in the repository has expired on <%asset.expirationdate%> and should be reviewed. Link: <%asset.url%>. Thank you. Please do not reply to this email, but contact the administrator at <%registrar.email%> for details.
- **Name:** Asset Inactive
 - **Description:** Notifies submitter/subscriber(s) that asset has been marked inactive.
 - **From:** User updating the asset to Inactive
 - **To:** User logged in that submits asset
 - **Content:** "The asset <%asset.name%> has been marked inactive."
- **Name:** Asset Registered
 - **Description:** Notifies submitter that asset has been registered.
 - **From:** Registrar email address
 - **To:** User logged in that submits asset
 - **Content:** "The asset <%asset.name%> has been registered."
- **Name:** Asset Retired
 - **Description:** Notifies submitter/subscriber(s) that asset has been marked retired.
 - **From:** User updating the asset to Retired
 - **To:** User logged in that submits asset
 - **Content:** "The asset <%asset.name%> has been retired."
- **Name:** Asset Submission Rejection
 - **Description:** Notifies submitter that asset has been rejected.
 - **From:** User logged in that rejects asset
 - **To:** User that submits asset
 - **Content:** "Your submission of the asset <%asset.name%> has been rejected."
- **Name:** Asset Tab Approved
 - **Description:** Notifies Registrar that tab has been approved.
 - **From:** User logged in that approves tab
 - **To:** Registrar email address
 - **Content:** "The tab <%asset.tab%> for the asset <%asset.name%> has been approved."
- **Name:** Asset Tab Unapproved
 - **Description:** Notifies user assigned to asset and Registrar that tab has been unapproved.
 - **From:** User logged in that submits asset
 - **To:** Registrar email address, User(s) that is/are assigned to asset
 - **Content:** "The tab <%asset.tab%> for the asset <%asset.name%> has been unapproved."
- **Name:** Asset Unaccepted
 - **Description:** Notifies submitter that asset has been unaccepted.
 - **From:** User who unaccepted the asset
 - **To:** User who submitted the asset
 - **Content:** "The asset <%asset.name%> has been unaccepted."
- **Name:** Asset Unassign
 - **Description:** Notifies user assigned to asset that they have been removed from asset.
 - **From:** User logged in that unassigns user
 - **To:** User that is unassigned from asset
 - **Content:** "The asset <%asset.name%> is no longer assigned to you."

- **Name:** Asset Unregistered
 - **Description:** Notifies submitter that asset as been unregistered
 - **From:** Registrar email address
 - **To:** User that submitted the asset
 - **Content:** "The asset <%asset.name%> has been unregistered."
-
- **Name:** Asset Unsubmitted
 - **Description:** Notifies submitter that asset has been unsubmitted.
 - **From:** User logged in that unsubmitted the asset
 - **To:** User that submitted the asset
 - **Content:** "The asset <%asset.name%> has been moved to the Unsubmitted queue."
-
- **Name:** Asset Used
 - **Description:** Notifies the contact specified in the asset **Notification Email** field that the asset has been used.
 - **From:** User who has indiated usage of an asset
 - **To:** User who is identified on the asset as the owner/maintainer
 - **Content:** <%user.name%> has used asset <%asset.name%> in a project.
-
- **Name:** Compliance Template Applied
 - **Description:** Notifies project leaders when compliance template applied to project.
 - **From:** Registrar email address
 - **To:** User who is identified as the Project Leader on the project
 - **Content:** "The compliance template <%asset.name%> has been applied to the project <%project.name%> by <%updatedby.name%>."
-
- **Name:** Metadata of asset has changed
 - **Description:** Notifies the registrar and the users assigned to the asset that the metadata has changed.
 - **From:** Registrar email address
 - **To:** Registrar and users who are assigned to an asset
 - **Content:** "The asset, <%asset.name%> (<%asset.version%>) in the repository has been updated with new metadata. The metadata attribute <%asset.metadata.attr.name%> of this asset changed from <%asset.metadata.attr.oldvalue%> to <%asset.metadata.attr.newvalue%>. Link: <%asset.url%>. Thank you. Please do not reply to this email, but contact the administrator at <%registrar.email%> for details."
-
- **Name:** New Asset Version under development
 - **Description:** Notifies subscribers when a new version of an asset is being developed.
 - **From:** Registrar email address
 - **To:** Users who have subscribed to an asset
 - **Content:** "A new version of <%asset.name%> is under development. You will be notified again when this version is registered."
-
- **Name:** New Version Registered
 - **Description:** Notifies subscribed user that new version of asset has been Registered.
 - **From:** Registrar email address
 - **To:** Subscribed user that used-downloaded an asset and selected checkbox to subscribe to previous version of asset
 - **Content:** "A new registered version of the asset <%primaryasset.name%> is now available in AquaLogic Enterprise Repository, named <%secondaryasset.name%>. You are being sent this notification because you previously subscribed to <%primaryasset.name%>."
-
- **Name:** Prior to Expiration
 - **Description:** Notifies the registrar and the users assigned to the asset that it is due for expiration.

- **From:** Registrar email address
 - **To:** Registrar and users who are assigned to an asset
 - **Content:** "The asset <%asset.name%> (<%asset.version%>) in the repository will expire on <%asset.expirationdate%>. Please take action prior to expiration. Link: -<%asset.url%>=. Thank you. Please do not reply to this email, but contact the administrator at <%registrar.email%> for details."
- **Name:** Registration Status Unchanged
 - **Description:** Notifies the registrar and the users assigned to the asset that the registration status '<%asset.reg.status%>' has remained unchanged for more than <%action.pending.days%> days.
 - **From:** Registrar and users who are assigned to an asset
 - **To:** Registrar email address
 - **Content:** "The current registration status of asset, <%asset.name%> (<%asset.version%>) in the repository is '<%asset.reg.status%>' and it has remained unchanged for more than <%action.pending.days%> days. Please take action. Link: <%asset.url%>. Thank you. Please do not reply to this email, but contact the administrator at <%registrar.email%> for details."
- **Name:** Repository Submission
 - **Description:** Notifies registrar that new asset has been submitted through the **Submit an Asset** link on the **Assets** screen.
 - **From:** User submitting asset through the **Submit an Asset** link on the **Assets** screen
 - **To:** Registrar email address
 - **Content:** "<%user.name%> submitted the Asset <%asset.name%> using the Asset Submission Tool."
- **Name:** Status of expired asset has changed
 - **Description:** Notifies the registrar and the users assigned to the expired asset that the status has changed.
 - **From:** Registrar and users who are assigned to an asset
 - **To:** Registrar email address
 - **Content:** "The asset, <%asset.name%> (<%asset.version%>) in the repository has expired on <%asset.expirationdate%>, and is now '<%asset.status%>'. Link: <%asset.url%>. Thank you. Please do not reply to this email, but contact the administrator at <%registrar.email%> for details."
- **Name:** Usage Query 1
 - **Description:** Queries the asset consumer regarding the intended use of the asset.
 - **From:** Registrar email address
 - **To:** User who indicated use of the asset
 - **Content:** "Please visit <%followup_url%>?id=<%pcid%>&uid=<%uid%> to update the status of your usage of the asset <%asset.name%> for use in <%project.name%>."
- **Name:** Usage Query 2
 - **Description:** Queries the asset consumer again regarding the intended use of the asset.
 - **From:** Registrar email address
 - **To:** User who indicated use of the asset
 - **Content:** "Please visit <%followup_url%>?id=<%pcid%>&uid=<%uid%> to update the status of your usage of the asset <%asset.name%> for use in= <%project.name%>="."
- **Name:** Usage Reassigned
 - **Description:** Notifies the user to whom an asset usage record has been reassigned.
 - **From:** Registrar email address
 - **To:** User to whom the usage information has been reassigned.
 - **Content:** "As a result of an asset reassignment, the asset <%asset.name%> in the project <%project.name%> has been assigned to you."

- **Name:** New user notification - Please note this email template is not editable and is not found in the email template section of the **Admin** screen.
- **Description:** Notifies Access Administrator that new user has been created.
- **From:** Repository
- **To:** Access Administrator
- **Content:** "The following accounts have been added to the Repository as unapproved users. Please log into AquaLogic Enterprise Repository to update their status: user, flash (flashline@flashline.com)."

Notifications by Role

- **User**
 - *Usage Query 1*
 - Queries the asset consumer regarding the intended use of the asset.
 - *Usage Query 2*
 - Depending on the response to Usage Query 1, asset consumers may receive a second query regarding the intended use of the asset.
 - *Usage Reassigned*
 - Notifies the user to whom an asset usage record has been reassigned. (in a project)
- **Advanced Submitter**
 - *Asset Accepted*
 - Notifies the submitter that the asset has been accepted
 - *Asset Active*
 - Notifies the submitter and subscribers that the asset has been marked active.
 - *Asset Deletion*
 - Notifies the submitter and subscribers that the asset has been deleted.
 - *Asset Inactive*
 - Notifies the submitter and subscribers that the asset has been marked inactive.
 - *Asset Registered*
 - Notifies the submitter that an asset has been registered.
 - *Asset Retired*
 - Notifies the submitter and subscribers that the asset has been retired.
 - *Asset Unaccepted*
 - Notifies the submitter that the asset has been unaccepted.
 - *Asset Unregistered*
 - Notifies the submitter that an asset has been unregistered.
 - *Asset Unsubmitted*
 - Notifies the submitter that the asset has been sent to the Unsubmitted queue.
 - *Asset Used*
 - Notifies the contact specified in the asset Notification Email field that the asset has been used (float - could be other role)
 - *Asset Submission Rejection*
 - Notifies the submitter that the asset has been rejected.
- **Registrar**
 - *All Asset Tabs Approved*
 - Notifies the registrar and the users assigned to the asset that all tabs have been approved.
 - *Asset Tab Approved*

- Notifies the registrar that a specific tab has been approved.
- *Asset Tab Unapproved*
 - Notifies the registrar that a specific tab has been unapproved (for both registered and unregistered assets).
- *Repository submission*
 - Notifies the registrar of an asset submission.
- *Asset Editor submission*
 - Notifies the registrar of an asset submission via the Asset Editor.

- **Subscribers**

- *Asset Active*
 - Notifies the submitter and subscribers that the asset has been marked active.
- *Asset Deletion*
 - Notifies the submitter and subscribers that the asset has been deleted.
- *Asset Inactive*
 - Notifies the submitter and subscribers that the asset has been marked inactive.
- *Asset Retired*
 - Notifies the submitter and subscribers that the asset has been retired.
- *New Asset Version under development*
 - Notifies subscribers when a new version of an asset is being developed.
- *New Version Registered*
 - Notifies subscribers that a new version of the asset is registered.
- *Asset Registered*
 - Notifies the submitter that an asset has been registered.
- *Asset Unregistered*
 - Notifies the submitter that an asset has been unregistered.

- **Assignees**

- *Asset Assign*
 - Notifies users that the asset has been assigned to them for processing.
- *All Asset Tabs Approved*
 - Notifies the registrar and the users assigned to the asset that all tabs have been approved.
- *Asset Tab Unapproved*
 - Notifies the registrar and the users assigned to the asset that a specific tab has been unapproved (for unregistered assets only).
- *Asset Unassign*
 - Notifies users that were previously assigned to an asset that they have been unassigned.

- **Project Leaders**

- *Compliance Template Applied*
 - Notifies project leaders when a compliance template has been applied to a project.

Editing Email Templates

The procedure begins on the AquaLogic Enterprise Repository **Admin** screen.

1. Click **Email Templates** in the **Admin** sidebar.

The list of email templates appears in the upper frame of the main pane.

The screenshot displays the AquaLogic Enterprise Repository Admin interface. On the left is a sidebar with navigation options: Users, Sessions, Roles, Departments, Basic Access Settings, Custom Access Settings, System Settings, Email Templates (highlighted), Import/Export, and SFID Manager. The main pane is divided into two sections. The top section shows a table of email templates:

Name	Status	Description
All Asset Tabs Approved	Active	Notifies the registrar and the users assigned to the asset that all tabs have been approved.
Asset Accepted	Active	Notifies the submitter that the asset has been accepted.
Asset Active	Active	Notifies the submitter and subscribers that the asset has been marked active.

The bottom section is the 'Email Template: All Asset Tabs Approved' edit screen. It contains the following fields and options:

- Name:** All Asset Tabs Approved
- Description:** Notifies the registrar and the users assigned to the asset that all tabs have been approved.
- Status:** Active (dropdown menu)
- Subject:** All <{%assetname%}> tabs have been approved
- Mail From:** <{%updatedby.email%}>
- Message:** All tabs for the asset <{%asset.name%}> have been approved.

Below the message field, there is a character limit: (Max 4000 Characters). A 'Valid Substitutions' section lists the following placeholders:

- <{%asset.name%}> - The display name of the used asset
- <{%registrar.email%}> - The registrar's email address
- <{%updatedby.email%}> - Person updating the asset
- <{%updatedby.name%}> - The name of the person updating the asset
- <{%asset.tab%}> - The name of the asset tab being updated

At the bottom of the edit screen are 'Save' and 'Cancel' buttons.

2. Select the email template to be edited from the list.

The **Email Template** edit screen opens in the bottom frame.

Email Template: **All Asset Tabs Approved**

Name: All Asset Tabs Approved

Description: Notifies the registrar and the users assigned to the asset that all tabs have been approved.

Status: Active

Subject: All <%assetname%> tabs have been approved

Mail From: <%updatedby.email%>

Message: All tabs for the asset <%asset.name%> have been approved.

(Max: 4000 Characters)

Valid Substitutions:

- <%asset.name%> - The display name of the used asset
- <%registrar.email%> - The registrar's email address
- <%updatedby.email%> - Person updating the asset
- <%updatedby.name%> - The name of the person updating the asset
- <%asset.tab%> - The name of the asset tab being updated

3. Use the **Status** drop-down to activate/deactivate the email message.
4. Edit the template information as necessary.

Notes on editing

- The **Status** field can be set to *Active* or *Inactive*. When inactive, no email notification will be sent for the specified event. *Active* is the default status.
- Substitutions are dynamic variables that can be placed within the subject, message, and *Mail From* email address. When the notification is sent, these variables will be replaced with the appropriate values. The following example demonstrates the syntax for entering a substitution for the name of the asset:

You have submitted the asset called <%asset.name%>

A list of acceptable substitutions is displayed with each email notification on the **Email Templates** screen.