#### **Oracle® JRockit Real Time**

Installing Oracle JRockit Real Time 3.1.0

April 2009



Oracle JRockit Real Time Installation Guide, 3.1.0

Copyright © 2007, 2009, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

## **Contents**

## Installing Oracle JRockit Real Time

| Note on Oracle JRockit Real Time Installation                 |
|---|
| Supported Configurations                                      |
| Notation Used in this Guide                                   |
| Installing and Uninstalling JRockit Real Time                 |
| Installing JRockit Real Time                                  |
| To install JRockit Real Time                                  |
| To Start JRockit Mission Control (Windows 32-bit x86)         |
| Adding JRockit Real Time to Your Path                         |
| Uninstalling JRockit Real Time                                |
| Uninstalling Windows Versions                                 |
| Uninstalling Windows Versions from the Command Line           |
| Uninstalling Linux and Solaris Versions from the Command Line |
| Installing and Uninstalling JRockit Real Time in Console Mode |
| Installing JRockit Real Time in Console Mode                  |
| Uninstalling JRockit Real Time in Console Mode                |
| Installing and Uninstalling JRockit Real Time in Silent Mode  |
| The silent.xml File   |
| Installing JRockit Real Time in Silent Mode                   |
| Uninstalling JRockit Real Time in Silent Mode11               |
| Special Note About Installing on Linux or Solaris             |
| Ensure the Installer is Executable                            |
|   |

| Acquire Root Access for System Wide Installation       | 11 |
|--|----|
| Default Location of System Preferences                 | 11 |
| Integration with Oracle Universal Installer            | 12 |
| Attaching JRockit Real Time to the Central Inventory   | 12 |
| Detaching JRockit Real Time from the Central Inventory | 13 |

# Installing Oracle JRockit Real Time

This document describes how to install Oracle JRockit Real Time as a standalone application. It includes information on the following subjects:

- Note on Oracle JRockit Real Time Installation
- Supported Configurations
- Notation Used in this Guide
- Installing and Uninstalling JRockit Real Time
- Installing and Uninstalling JRockit Real Time in Console Mode
- Installing and Uninstalling JRockit Real Time in Silent Mode
- Special Note About Installing on Linux or Solaris

**Note:** JRockit Real Time can be used by any application and does not interact with or create an Oracle registry.

## **Note on Oracle JRockit Real Time Installation**

This document shows how to install JRockit Real Time, which includes the Oracle JRockit JDK, the Oracle JRockit JRE, and the Oracle JRockit JVM. The Oracle JRockit JVM is installed as a part of many Oracle products. Refer to the documentation for those products for installation instructions.

## **Supported Configurations**

For a complete list of supported configurations, please visit:

http://edocs.bea.com/jrockit/jrdocs/suppPlat/supp\_plat.html

#### **Notation Used in this Guide**

Throughout this document, JRockit Real Time versions are defined with the following notation:

```
jrrt-<jrrt_version>-<java_version>
```

For example:

jrrt-3.1.0-1.6.0

In this example, the product is JRockit Real Time 3.1.0 for Java SE 6.

## Installing and Uninstalling JRockit Real Time

This section explains how to install and uninstall a standalone version of JRockit Real Time in GUI mode for the following platforms:

- Microsoft Windows 32-bit x86 and 64-bit Xeon/AMD64.
- Red Hat Linux 32-bit x86 and 64-bit Xeon/AMD64.
- Sun Solaris on 64-bit SPARC.

**Note:** If you are installing on Linux and Solaris, please refer to Default Location of System Preferences for information on where to find the system preferences.

## **Installing JRockit Real Time**

In the following procedure you will run the self-installing executable (Windows) or the self-extracting binary (Solaris and Linux). The screen shots are taken from a Windows installation of JRockit Real Time. Table 1 lists the installers.

Table 1 JRockit Real Time Installers by Version and Platform

| On                                 | For Java SE version | Use                                  |
|------------------------------------|---------------------|--------------------------------------|
| Windows 32-bit x86                 | 1.4.2               | jrrt-3.1.0-1.4.2-windows-ia32.exe    |
|                                    | 5.0                 | jrrt-3.1.0-1.5.0-windows-ia32.exe    |
|                                    | 6                   | jrrt-3.1.0-1.6.0-windows-ia32.exe    |
| Windows 64-bit Xeon/AMD64          | 5.0                 | jrrt-3.1.0-1.5.0-windows-x64.exe     |
|                                    | 6                   | jrrt-3.1.0-1.6.0-windows-x64.exe     |
| Red Hat Linux 32-bit x86           | 1.4.2               | jrrt-3.1.0-1.4.2-linux-ia32.bin      |
|                                    | 5.0                 | jrrt-3.1.0-1.5.0-linux-ia32.bin      |
|                                    | 6                   | jrrt-3.1.0-1.6.0-linux-ia32.bin      |
| Red Hat Linux 64-bit<br>Xeon/AMD64 | 5.0                 | jrrt-3.1.0-1.5.0-linux-x64.bin       |
|                                    | 6                   | jrrt-3.1.0-1.6.0-linux-x64.bin       |
| Sun Solaris on 64-bit Sparc        | 1.4.2               | jrrt-3.1.0-1.4.2-solaris-sparcv9.bin |
|                                    | 5.0                 | jrrt-3.1.0-1.5.0-solaris-sparcv9.bin |
|                                    | 6                   | jrrt-3.1.0-1.6.0-solaris-sparcv9.bin |

#### To install JRockit Real Time

- 1. Make sure you have downloaded the appropriate version of JRockit Real Time for your operating system (see Table 1).
- 2. On your local drive, locate the executable file for the version of JRockit Real Time you want to install.

**Note:** If you install JRockit Real Time on Linux or Solaris please refer to Ensure the Installer is Executable.


3. Run the installer.

The install process begins and the Oracle installer window appears, followed by the **Welcome** window.

#### 4. Click Next.

The Choose Product Installation Directories window appears (see Figure 1-2).

Figure 1-2 Choose Product Installation Directories Window



5. Click **Next** if you are satisfied with the suggested product installation directory.

**Note:** If you want a different location for the installation you can pick one by clicking **Browse** or type a new directory into the **Product Installation Directory** field. By clicking **Discard Changes**, you set the selection back to the default directory.

The **Optional Components** window appears (see Figure 2).




Figure 2 Optional Components Window

- 6. Select which, if any, optional components you want to install with JRockit Real Time. Selecting:
  - **Demos and Samples** will install demo and sample files at:

```
[INSTALL_DIR]\demo
and
[INSTALL_DIR]\sample
```

**Note:** Sample files are not available in Oracle JRockit JDK 1.4.2.

 Source Code will install the file src.zip, containing the source code for the Java platform at:

```
[INSTALL_DIR]\src.zip
```

7. Click **Next** (the installation starts immediately after you click **Next**).

The **Oracle Installer** window appears and the installation process continues, as indicated on the progress meter in the lower right corner of the window (see Figure 2-1).

Figure 2-1 Oracle Installer Window with Progress Meter



When the installation is complete, the **Installation Complete** window appears.

#### 8. Click Done.

JRockit Real Time is now installed.

#### To Start JRockit Mission Control (Windows 32-bit x86)

If you have installed JRockit Real Time you can start Oracle JRockit Mission Control 3.1.0 from the **Start** menu.

#### **Adding JRockit Real Time to Your Path**

Once you have installed JRockit Real Time, you need to add it to your path.

#### Use this command for Windows platforms:

**Note:** This example assumes that you are using the Windows command prompt (DOS) or compatible command shell and have selected the default product installation directory.

```
set PATH=%ProgramFiles%\JRockit Real
Time\jrrt-<jrrt_version>-<java_version>\bin;%PATH%
```

#### Use this command for Linux and Solaris platforms:

**Note:** This example assumes that you are using the UNIX bash shell or compatible command shell and have selected the default product installation directory.

export PATH=\$HOME/jrrt-<jrrt\_version>-<java\_version>/bin:\$PATH

## **Uninstalling JRockit Real Time**

This section describes how to uninstall the Windows, Linux, and Solaris versions of JRockit Real Time.

#### **Uninstalling Windows Versions**

To uninstall JRockit Real Time, do the following:

- 1. Open the **Start** menu and select **All Programs**.
- 2. Select Oracle JRockit Real Time [version]>Uninstall Oracle JRockit Real Time [version].

The **Oracle Uninstaller** confirmation message appears.

Click OK.

The **Oracle Uninstaller** appears and the uninstall process commences.

Click OK.

JRockit Real Time is removed from your computer.

#### **Uninstalling Windows Versions from the Command Line**

To uninstall JRockit Real Time from the command line, run the following command from a console window:

%SystemRoot%\Installer\Oracle\jrrt-<jrrt\_version>-<java\_version>-<arch>\un
install.exe

#### Uninstalling Linux and Solaris Versions from the Command Line

To uninstall Linux and Solaris versions of JRockit Real Time, do the following:

- 1. Ensure you are one step below the appropriate JRockit Real Time product directory.
- 2. At the command line, enter:

```
rm -rf jrrt-<jrrt_version>-<java_version>
```

JRockit Real Time is removed from your computer.

# Installing and Uninstalling JRockit Real Time in Console Mode

This section describes how to install JRockit Real Time using console mode, rather than from a GUL

#### **Installing JRockit Real Time in Console Mode**

To install JRockit Real Time in console mode, do the following:

- Make sure you have downloaded the appropriate version of JRockit Real Time for your operating system (see Table 1).
- 2. On your local drive, locate the executable file for the version of JRockit Real Time you want to install:

**Note:** If you install JRockit Real Time on Linux or Solaris please refer to Ensure the Installer is Executable.

- 3. Open a command window or console on your computer.
- 4. Change to the directory from which you want to install JRockit Real Time.
- 5. At the command line, enter:

```
jrrt-<jrrt_version>-<java_version>-<platform>.<ext> -mode=console
where <ext> is the file name extension; that is, exe on Windows and bin on Linux and
Solaris.
```

The system responds:

```
Extracting 0%......100%
```

Once the extraction process is complete, the system will prompt you through the installation, replicating the procedures described in Installing and Uninstalling JRockit Real Time.

**Note:** If you don't specify -mode=console at the command line, the installer will revert to GUI mode, as described in Installing and Uninstalling JRockit Real Time.

## **Uninstalling JRockit Real Time in Console Mode**

To uninstall Windows versions, use one of the methods described in Uninstalling Windows Versions and Uninstalling Windows Versions from the Command Line.

To uninstall Linux and Solaris versions, use the method described in Uninstalling Linux and Solaris Versions from the Command Line.

# Installing and Uninstalling JRockit Real Time in Silent Mode

The silent installation mode lets you set installation configurations only once and then use those configurations to duplicate the installation on many machines. During installation in silent mode, the installation program reads installation options from an XML file that you create prior to beginning the installation (see The silent.xml File). The installation program does not display any configuration options during the installation process. For more information on silent mode, please refer to "What Is Silent-Mode Installation?" in the Oracle WebLogic Server *Installation Guide*.

#### The silent.xml File

For a silent mode installation to be successful, you will need to create the file silent.xml and store it on your computer. This file contains the values you want included in your setup. Listing 1 shows an example of a silent.xml file for JRockit Real Time 3.1.0 for Java SE 6.

#### Listing 1 Example of a silent.xml File

```
<!--
    Optional installation of Demos and Samples
        Use "true", or "yes", to install this optional component.
        Use "false", or "no", to skip this optional component. The default is
        "false".
        This option is available on all platforms.
-->
<data-value name="INSTALL_DEMOS_AND_SAMPLES" value="false" />
<!--
        Optional installation of Source Code
            Use "true", or "yes", to install this optional component.
            Use "false", or "no", to skip this optional component. The default is
            "false".
            This option is available on all platforms.
-->
<data-value name="INSTALL_SOURCE_CODE" value="false" />
</input-fields>
</domain-template-descriptor>
```

## **Installing JRockit Real Time in Silent Mode**

To install JRockit Real Time in silent mode, do the following (this procedure assumes that silent.xml is stored in the same directory as the JRockit Real Time installer):

- 1. Make sure you have downloaded the appropriate version of JRockit Real Time for your operating system (see Table 1).
- 2. On your local drive, locate the executable file for the version of JRockit Real Time you want to install:

**Note:** If you install JRockit Real Time on Linux or Solaris please refer to Ensure the Installer is Executable.

- 3. Open a command window or console on your computer.
- 4. Change to the directory from which you want to install JRockit Real Time.
- 5. At the command line, enter:

```
jrrt-<jrrt_version>-<java_version>-<platform>.<ext> -mode=silent
-silent_xml="silent.xml"
```

where <ext> is the file name extension; that is, exe on Windows and bin on Linux and Solaris.

You will receive a message advising that files are being extracted and no other confirmation.

To confirm the successful installation on Windows, you can look for **Oracle JRockit Real Time** [version] in your Start menu.

Note: If you want to create an install log, add the option -log=log.log at the end of the command.

## **Uninstalling JRockit Real Time in Silent Mode**

To uninstall Windows versions, use one of the methods described in Uninstalling Windows Versions and Uninstalling Windows Versions from the Command Line.

To uninstall Linux and Solaris versions, use the method described in Uninstalling Linux and Solaris Versions from the Command Line.

## **Special Note About Installing on Linux or Solaris**

If you are installing JRockit Real Time on either a Linux or Solaris machine, note the following information.

#### **Ensure the Installer is Executable**

If you install JRockit Real Time on Linux or Solaris by using the .bin file, you need to ensure the file is executable. You can use chmod +x <filename> to make the file executable.

## **Acquire Root Access for System Wide Installation**

If you choose to install JRockit Real Time on Linux or Solaris into a system-wide location such as /usr/local, you must first become the root user to gain the necessary permissions. If you do not have root access, simply install JRockit Real Time into a directory where you have permission to write, for example, your home directory.

## **Default Location of System Preferences**

When installing on Linux and Solaris, the default location for system preferences will be:

```
[JAVA_HOME]/.systemPrefs
where [JAVA_HOME]=[INSTALL_DIR]/jre.
```

unless the user is root, in which case it will be /etc/.java/.systemPrefs.

## **Integration with Oracle Universal Installer**

Starting with JRockit Real Time 3.1.0, each product installation directory is also an Oracle home, allowing additional product registration with the Oracle Central Inventory. The Central Inventory contains information about all installed Oracle products on the same host and can be managed by running the Oracle Universal Installer.

**Note:** The examples assume that you have installed Oracle Universal Installer either directly or indirectly as part of another Oracle product. For more information on how to start the Oracle Universal Installer see:

http://download.oracle.com/docs/cd/B28359\_01/em.111/b31207/oui4\_product\_instal 1.htm#i1005879

The Oracle home name in the examples is supposed to be unique between all Oracle products installed on the same host and is obtained from the name of the default product installation directory by replacing dashes by underscores, removing dots in product version numbers, and attaching the name of the architecture.

## Attaching JRockit Real Time to the Central Inventory

Once you have installed JRockit Real Time, you can attach it to the Central Inventory by using the Oracle Universal Installer.

#### Use this command for Windows platforms:

**Note:** This example assumes that you are using the Windows command prompt (DOS) or compatible command shell and have selected the default product installation directory.

```
setup.exe -noconsole -attachHome \
ORACLE_HOME="%ProgramFiles%\JRockit Real
Time\jrrt-<jrrt_version>-<java_version>" \
ORACLE_HOME_NAME="jrrt_<jrrt_version_compact>_<java_version_compact>_<arch>"
```

#### **Use this command for Linux and Solaris platforms:**

**Note:** This example assumes that you are using the UNIX bash shell or compatible command shell and have selected the default product installation directory.

```
./runInstaller -attachHome \
ORACLE_HOME="$HOME/jrrt-<jrrt_version>-<java_version>" \
ORACLE_HOME_NAME="jrrt_<jrrt_version_compact>_<java_version_compact>_<arch>"
```

## **Detaching JRockit Real Time from the Central Inventory**

Before you uninstall JRockit Real Time you should ensure that it is detached from the Central Inventory.

#### Use this command for Windows platforms:

This example assumes that you are using the Windows command prompt (DOS) or compatible command shell and have selected the default product installation directory.

```
setup.exe -noconsole -detachHome \
ORACLE_HOME="%ProgramFiles%\JRockit Real
Time\jrrt-<jrrt_version>-<java_version>" \
ORACLE_HOME_NAME="jrrt_<jrrt_version_compact>_<java_version_compact>_<arch>"
```

#### Use this command for Linux and Solaris platforms:

This example assumes that you are using the UNIX bash shell or compatible command shell and have selected the default product installation directory.

```
./runInstaller -detachHome \
ORACLE_HOME="$HOME/jrrt-<jrrt_version>-<java_version>" \
ORACLE_HOME_NAME="jrrt_<jrrt_version_compact>_<java_version_compact>_<arch>"
```