



# BEA AquaLogic® Service Bus

**Using the AquaLogic  
Service Bus Plug-in for  
WorkSpace Studio**



# Contents

## 1. Introduction to ALSB

## 2. Tasks

Working with Projects, Folders, Resources, and Configurations . . . . .	2-1
Editing Resources . . . . .	2-2
Cloning ALSB Projects and Folders . . . . .	2-3
Creating ALSB Configuration Projects . . . . .	2-3
Creating ALSB Projects . . . . .	2-3
Creating Custom Resources . . . . .	2-4
Creating JNDI Provider Resources . . . . .	2-4
Creating Message Format Files . . . . .	2-4
Editing JNDI Provider Resources . . . . .	2-4
Exporting Resources . . . . .	2-4
Generating an Effective WSDL . . . . .	2-4
Modifying JAR Dependencies . . . . .	2-5
Importing Resources . . . . .	2-5
Creating Servers . . . . .	2-5
Creating Service Account Resources . . . . .	2-5
Creating Service Key Provider Resources . . . . .	2-5
Creating SMTP Server Resources . . . . .	2-6
Creating XQuery Transformations . . . . .	2-6
Creating XSL Transformations . . . . .	2-6

Working with Business Services . . . . .	2-6
Creating Business Services . . . . .	2-6
Editing Business Services . . . . .	2-7
Working with Proxy Services . . . . .	2-7
Creating Proxy Services . . . . .	2-7
Editing Proxy Services . . . . .	2-8
Working with Alert Destinations . . . . .	2-8
Creating Alert Destinations . . . . .	2-8
Editing Alert Destinations . . . . .	2-9
Adding E-mail Recipients to Alert Destinations . . . . .	2-9
Adding JMS Destinations to Alert Destinations . . . . .	2-9
Working with Proxy Service Message Flows . . . . .	2-9
Constructing Proxy Service Message Flows . . . . .	2-11
Adding and Configuring Alert Actions in Message Flows . . . . .	2-11
Adding and Configuring Assign Actions in Message Flows . . . . .	2-12
Adding and Configuring Conditional Branch Nodes in Message Flows . . . . .	2-12
Adding and Configuring Delete Actions in Message Flows . . . . .	2-13
Adding and Configuring Dynamic Publish Actions in Message Flows . . . . .	2-13
Adding and Configuring Dynamic Routing Actions in Message Flows . . . . .	2-14
Adding and Configuring Error Handlers in Message Flows . . . . .	2-14
Adding and Configuring For-Each Actions in Message Flows . . . . .	2-15
Adding and Configuring If-Then Actions in Message Flows . . . . .	2-16
Adding and Configuring Insert Actions in Message Flows . . . . .	2-16
Adding and Configuring Java Callout Actions in Message Flows . . . . .	2-17
Adding and Configuring Log Actions in Message Flows . . . . .	2-17
Adding and Configuring MFL Transform Actions in Message Flows . . . . .	2-18
Adding and Configuring Operational Branch Nodes in Message Flows . . . . .	2-18
Adding and Configuring Pipeline Pair Nodes in Message Flows . . . . .	2-19

Adding and Configuring Publish Actions in Message Flows . . . . .	2-19
Adding and Configuring Publish Table Actions in Message Flows . . . . .	2-20
Adding and Configuring Raise Error Actions in Message Flows . . . . .	2-21
Adding and Configuring Rename Actions in Message Flows . . . . .	2-22
Adding and Configuring Replace Actions in Message Flows . . . . .	2-22
Adding and Configuring Reply Actions in Message Flows . . . . .	2-23
Adding and Configuring Report Actions in Message Flows . . . . .	2-23
Adding and Configuring Resume Actions in Message Flows . . . . .	2-24
Adding and Configuring Route Nodes in Message Flows . . . . .	2-24
Adding and Configuring Routing Actions in Message Flows . . . . .	2-25
Adding and Configuring Routing Options Actions in Message Flows . . . . .	2-25
Adding and Configuring Routing Table Actions in Message Flows . . . . .	2-26
Adding and Configuring Service Callout Actions in Message Flows . . . . .	2-26
Adding and Configuring Skip Actions in Message Flows . . . . .	2-27
Adding and Configuring Stages in Message Flows . . . . .	2-27
Adding and Configuring Transport Headers Actions in Message Flows . . . . .	2-28
Adding and Configuring Validate Actions in Message Flows . . . . .	2-28
Working with MQ Connections . . . . .	2-29
Adding MQ Connections . . . . .	2-29
Editing MQ Connections . . . . .	2-29
Working with UDDI Registries . . . . .	2-30
Adding UDDI Registries . . . . .	2-30
Configuring UDDI Registries . . . . .	2-30
Importing Business Services From a UDDI Registry . . . . .	2-30
Working with Split-Join . . . . .	2-31
Introduction to Split-Join . . . . .	2-31
Designing a Split-Join . . . . .	2-31
Designing a Static Split-Join . . . . .	2-32

Designing a Dynamic Split-Join . . . . .	2-38
Creating a New Split-Join . . . . .	2-45
Configuring the Start Node . . . . .	2-46
Configuring a Receive . . . . .	2-48
Creating an Assign . . . . .	2-49
Creating an Invoking External Service . . . . .	2-51
Creating a Parallel . . . . .	2-53
Creating a For Each . . . . .	2-54
Creating an If Activity . . . . .	2-55
Creating an Error Handler . . . . .	2-59
Creating a Raise Error . . . . .	2-60
Configuring a Reply . . . . .	2-60
About Scope . . . . .	2-62
Exporting and Testing a Split-Join . . . . .	2-63

### 3. User Interface Reference

Alerts . . . . .	3-1
Alert Destination editor . . . . .	3-1
Edit E-mail Recipient page . . . . .	3-2
Edit JMS Destination page . . . . .	3-4
AquaLogic Business Service Configuration . . . . .	3-4
Business Service General Configuration page . . . . .	3-4
Business Service Message Type Configuration page . . . . .	3-7
Business Service Service Policy Configuration page . . . . .	3-9
Business Service SOAP Binding Configuration page . . . . .	3-9
Business Service Transport Configuration page . . . . .	3-9
AquaLogic Proxy Service Configuration . . . . .	3-13
Proxy Service General Configuration page . . . . .	3-13

Proxy Service Message Level Security Configuration page . . . . .	3-16
Proxy Service Message Type Configuration page. . . . .	3-19
Proxy Service Operation Selection Configuration page . . . . .	3-22
Proxy Service Service Policy Configuration page . . . . .	3-25
Proxy Service SOAP Binding Configuration page . . . . .	3-26
Proxy Service Transport Configuration page . . . . .	3-27
ALSB Configurations and Projects. . . . .	3-30
ALSB Configurations view. . . . .	3-31
New AquaLogic Service Bus Configuration Project wizard. . . . .	3-31
ALSB Configuration page. . . . .	3-32
New AquaLogic Service Bus Project wizard . . . . .	3-33
Custom Resources. . . . .	3-33
New Custom Resource wizard . . . . .	3-34
New Custom Resource Editor . . . . .	3-34
New Custom Resource - Resource Type page. . . . .	3-34
Custom MQ Resource Configuration page . . . . .	3-34
Export wizard . . . . .	3-36
Export wizard - ALSB Configuration JAR Export page. . . . .	3-36
Export wizard - Export to Server - Select Resources page . . . . .	3-37
Export wizard - Export to Server - Review Resources page . . . . .	3-38
Import wizard . . . . .	3-38
Import wizard - Config JAR Import - Load Resources page . . . . .	3-39
Import wizard - Config JAR Import - Review Resources page . . . . .	3-39
Import wizard - Config ZIP Import - Load Resources page . . . . .	3-40
Import wizard - Config ZIP Import - Review Resources page . . . . .	3-41
Import wizard - URL Import - Load Resources page . . . . .	3-41
Import wizard - URL Import - Review Resources page . . . . .	3-41
JNDI Providers . . . . .	3-42

JNDI Provider Editor . . . . .	3-42
New JNDI Provider Resource wizard . . . . .	3-42
Message Flow Design Palette. . . . .	3-43
Message Flow Nodes . . . . .	3-44
Message Flow Route Actions - Communication Actions. . . . .	3-44
Message Flow Route Actions - Flow Control Actions . . . . .	3-45
Message Flow Stage Actions - Communication Actions . . . . .	3-45
Message Flow Stage Actions - Flow Control Actions . . . . .	3-46
Message Flow Stage Actions - Message Processing Actions . . . . .	3-47
Message Flow Stage Actions - Reporting Actions . . . . .	3-48
Message Flow Editor . . . . .	3-48
Alert Action Properties . . . . .	3-50
Assign Action Properties. . . . .	3-52
Conditional Branch Node Properties . . . . .	3-53
Delete Action Properties . . . . .	3-54
Dynamic Publish Action Properties . . . . .	3-55
Dynamic Routing Action Properties . . . . .	3-56
Error Handler Node Properties . . . . .	3-57
For-Each Action Properties. . . . .	3-58
If-Then Action Properties . . . . .	3-59
Insert Action Properties. . . . .	3-61
Java Callout Action Properties . . . . .	3-62
Log Action Properties . . . . .	3-64
Message Flow Properties- Comment . . . . .	3-65
Message Flow Properties - Namespaces. . . . .	3-66
Message Flow Properties - Variables . . . . .	3-66
MFL Transform Action Properties . . . . .	3-66
Operational Branch Node Properties . . . . .	3-67

Pipeline Pair Node Properties . . . . .	3-68
Publish Action Properties . . . . .	3-69
Publish Table Action Properties . . . . .	3-70
Raise Error Action Properties . . . . .	3-72
Rename Action Properties . . . . .	3-73
Replace Action Properties . . . . .	3-74
Reply Action Properties . . . . .	3-75
Report Action Properties . . . . .	3-76
Resume Action Properties . . . . .	3-78
Route Node Properties . . . . .	3-78
Routing Action Properties . . . . .	3-79
Routing Options Action Properties . . . . .	3-80
Routing Table Action Properties . . . . .	3-82
Service Callout Action Properties . . . . .	3-83
Skip Action Properties . . . . .	3-89
Stage Node Properties . . . . .	3-89
Transport Headers Action Properties . . . . .	3-90
Validate Action Properties . . . . .	3-94
Modify JAR Dependencies dialog . . . . .	3-95
SMTP Servers . . . . .	3-95
Edit SMTP Server page . . . . .	3-95
New SMTP Server Resource wizard . . . . .	3-96
UDDI Registry Configuration page . . . . .	3-96
Outline view - AquaLogic Service Bus . . . . .	3-97
Resource Management . . . . .	3-98
Preferences dialog - AquaLogic Service Bus - Type Associations page . . . . .	3-98
References view . . . . .	3-98
Select Clone Target dialog . . . . .	3-99

Select a Resource dialog . . . . .	3-99
New Service Key Provider Resource wizard . . . . .	3-100
New WS-Policy wizard . . . . .	3-100
Service Accounts . . . . .	3-101
New Service Account Resource wizard . . . . .	3-101
Service Account editor - General Configuration page . . . . .	3-102
Service Account editor - Static User Configuration page . . . . .	3-103
Service Account editor - User Mappings Configuration page . . . . .	3-103
Expression Editors . . . . .	3-104
XQuery/XSLT Expression Editor . . . . .	3-104
XPath Expression Editor . . . . .	3-105
Condition Editor . . . . .	3-105
Condition Builder page . . . . .	3-106
Expression page . . . . .	3-107
XQuery Resource page . . . . .	3-107
XSLT Resource page . . . . .	3-108
Variable Structures page . . . . .	3-109
Namespace Definitions page . . . . .	3-110
XQuery Functions page . . . . .	3-110
Add Variable Structure dialog . . . . .	3-110
New XSL Transformation wizard . . . . .	3-111
Split-Join User Interface Reference . . . . .	3-112
Split-Join Design Palette . . . . .	3-113
Split-Join Properties View - Error Handler . . . . .	3-114
Split-Join Properties View - External Services . . . . .	3-115
Split-Join Properties View - Assign . . . . .	3-115
Split-Join Properties View - Global Properties . . . . .	3-118
Split-Join Properties View - For Each . . . . .	3-118

Split-Join Properties View - If Activity . . . . .	3-120
Split-Join Process Properties View - If and Else If . . . . .	3-120
Split-Join Properties View - Invoke External Service . . . . .	3-120
Split-Join Properties View - Parallel . . . . .	3-122
Split-Join Properties View - Raise Error Page . . . . .	3-122
Split-Join Properties View - Receive Page . . . . .	3-122
Split-Join Properties View - Reply Page . . . . .	3-123
Split-Join Properties View - Scope . . . . .	3-125
Split-Join Properties View - Start Node . . . . .	3-126
Split-Join Properties View - Variable . . . . .	3-126
Assign Operation Dialog . . . . .	3-127
Copy Literal/XPath 1.0 Expression Dialog . . . . .	3-127
Counter Variable Dialog . . . . .	3-128
Create/Edit Variable Dialog . . . . .	3-128
Create Message Variable Dialog . . . . .	3-129
Delete Action Dialog . . . . .	3-129
Insert Action Dialog . . . . .	3-130
Replace Action Dialog . . . . .	3-130
Split-Join Wizard - New Split-Join . . . . .	3-131
Split-Join Wizard - Specify Operations . . . . .	3-131
Service Browser . . . . .	3-132
SOAP Fault Variable Dialog . . . . .	3-132
WSDL Browser . . . . .	3-132

## 4. Transport Configuration

<i>Protocol-Specific</i> Transport Configuration Pages . . . . .	4-1
DSP Transport Configuration page (Business Services) . . . . .	4-2
EJB Transport Configuration page (Business Services) . . . . .	4-3

E-Mail Transport Configuration page (Business Services) . . . . .	4-4
E-Mail Transport Configuration page (Proxy Services) . . . . .	4-5
File Transport Configuration page (Business Services) . . . . .	4-6
File Transport Configuration page (Proxy Services) . . . . .	4-7
FTP Transport Configuration page (Business Services) . . . . .	4-8
FTP Transport Configuration page (Proxy Services) . . . . .	4-9
HTTP Transport Configuration Page (Business Services) . . . . .	4-11
HTTP Transport Configuration Page (Proxy Services) . . . . .	4-13
JMS Transport Configuration page (Business Services) . . . . .	4-14
JMS Transport Configuration page (Proxy Services) . . . . .	4-17
JPD Transport Configuration page (Business Services) . . . . .	4-20
MQ Transport Configuration page (Business Services) . . . . .	4-22
MQ Transport Configuration page (Proxy Services) . . . . .	4-23
SB Transport Configuration page (Business Services) . . . . .	4-24
SB Transport Configuration page (Proxy Services) . . . . .	4-25
SFTP Transport Configuration page (Business Services) . . . . .	4-26
SFTP Transport Configuration page (Proxy Services) . . . . .	4-27
Tuxedo Transport Configuration page (Business Services) . . . . .	4-29
Tuxedo Transport Configuration page (Proxy Services) . . . . .	4-31
WS Transport Configuration page (Business Services) . . . . .	4-33
WS Transport Configuration page (Proxy Services) . . . . .	4-34

# Introduction to ALSB

ALSB is a configuration-based, policy-driven Enterprise Service Bus (ESB). It provides highly scalable and reliable service-oriented integration, service management, and traditional message brokering across heterogeneous IT environments. It combines intelligent message brokering with routing and transformation of messages, along with service monitoring and administration in a unified software product. For more information, see [BEA AquaLogic Service Bus Concepts and Architecture](#).

This documentation tells how to use the ALSB Plug-in for WorkSpace Studio to configure services and polices. These are design-time activities, so you do not need a running WebLogic Server instance. The Web-based ALSB Console, also provided with ALSB, provides the same design tools as the ALSB plug-in, and it also provides run-time activities such as monitoring. You need a running WebLogic Server instance to use the ALSB Console. See [Using the AquaLogic Service Bus Console](#).

## Introduction to ALSB

# Tasks

This section tells how to perform tasks in the AquaLogic Service Bus Plug-in for WorkSpace Studio:

- [“Working with Projects, Folders, Resources, and Configurations”](#) on page 2-1
- [“Working with Business Services”](#) on page 2-6
- [“Working with Proxy Services”](#) on page 2-7
- [“Working with Proxy Service Message Flows”](#) on page 2-9
- [“Working with MQ Connections”](#) on page 2-29
- [“Working with UDDI Registries”](#) on page 2-30
- [“Working with Split-Join”](#) on page 2-31

## Working with Projects, Folders, Resources, and Configurations

This section tells how to perform the following tasks:

- [“Editing Resources”](#) on page 2-2
- [“Cloning ALSB Projects and Folders”](#) on page 2-3
- [“Creating ALSB Configuration Projects”](#) on page 2-3

## Tasks

- “Creating ALSB Projects” on page 2-3
- “Creating Custom Resources” on page 2-4
- “Creating JNDI Provider Resources” on page 2-4
- “Creating Message Format Files” on page 2-4
- “Editing JNDI Provider Resources” on page 2-4
- “Editing JNDI Provider Resources” on page 2-4
- “Exporting Resources” on page 2-4
- “Generating an Effective WSDL” on page 2-4
- “Modifying JAR Dependencies” on page 2-5
- “Importing Resources” on page 2-5
- “Creating Servers” on page 2-5
- “Creating Service Account Resources” on page 2-5
- “Creating Service Key Provider Resources” on page 2-5
- “Creating SMTP Server Resources” on page 2-6
- “Creating XQuery Transformations” on page 2-6
- “Creating XSL Transformations” on page 2-6

See also the following information about working with other kinds of resources:

- “Working with Business Services” on page 2-6
- “Working with Proxy Services” on page 2-7
- “Working with Alert Destinations” on page 2-8
- “Working with MQ Connections” on page 2-29
- “Working with UDDI Registries” on page 2-30

## Editing Resources

Edit resources using the built-in editors. For example, edit a proxy service by double-clicking its name in the Project Explorer.

Do not manually edit resource files as text or XML files. This can result in unpredictable behavior. Do not manually edit these resource types:

- Alert Destination
- Business Service
- Custom Resources
- Proxy Service
- Service Account
- Service Key Provider
- Split-Join
- JNDI Provider
- SMTP Server
- UDDI Registry

## Cloning ALSB Projects and Folders

1. In the Project Explorer, right-click the ALSB project or folder you want to clone.
2. From the menu, select **AquaLogic Service Bus > Clone** to display the [Select Clone Target dialog](#). Enter information as appropriate.

## Creating ALSB Configuration Projects

In the ALSB perspective, select **File > New > ALSB Configuration Project** to display the [New AquaLogic Service Bus Configuration Project wizard](#). Enter information as appropriate.

## Creating ALSB Projects

In the ALSB perspective, select **File > New > ALSB Project** to display the [New AquaLogic Service Bus Project wizard](#). Enter information as appropriate.

**Note:** You can create an ALSB project in an ALSB configuration project only.

## Creating Custom Resources

In the ALSB perspective, select **File > New > Custom Resource** to display [New Custom Resource wizard](#). Enter information as appropriate.

**Note:** You can create a custom resource in an ALSB project only.

## Creating JNDI Provider Resources

In the ALSB perspective, select **File > New > JNDI Provider** to display the [New JNDI Provider Resource wizard](#). Enter information as appropriate.

**Note:** You can create a JNDI provider resource in an ALSB configuration project only.

## Creating Message Format Files

In the ALSB perspective, select **File > New > MFL** to display the New Message Format File wizard. Enter information as appropriate.

**Note:** You can create a message format file in an ALSB project only.

## Editing JNDI Provider Resources

1. In the Project Explorer, find the ALSB configuration project containing the JNDI provider resource you want to edit.
2. Double-click the name of the JNDI provider to display the [JNDI Provider Editor](#). Edit as appropriate.

## Exporting Resources

In the ALSB perspective, select **File > Export** to display the Export wizard. See:

- [Export wizard - ALSB Configuration JAR Export page](#)
- [Export wizard - Export to Server - Select Resources page](#)

## Generating an Effective WSDL

1. In the Project Explorer, find the proxy service or business service from which you want to generate the effective WSDL.
2. Right-click the name of the service and select **AquaLogic Service Bus > Generate Effective WSDL** from the menu.

3. Select a location and save the file.

## Modifying JAR Dependencies

1. In the Project Explorer, find the JAR file whose dependencies you want to modify.
2. Right-click the name of the file and select **AquaLogic Service Bus > Modify JAR Dependencies** from the menu.
3. Make modifications in the [Modify JAR Dependencies dialog](#).

## Importing Resources

In the ALSB perspective, select **File > Import** to display the Import wizard. See:

- [Import wizard - Config JAR Import - Load Resources page](#)
- [Import wizard - Config JAR Import - Review Resources page](#)
- [Import wizard - URL Import - Review Resources page](#)
- [Import wizard - Config ZIP Import - Load Resources page](#)
- [Import wizard - Config ZIP Import - Review Resources page](#)

## Creating Servers

In the ALSB perspective, select **File > New > Server** to display the New Server wizard.

## Creating Service Account Resources

In the ALSB perspective, select **File > New > Service Account** to display the [New Service Account Resource wizard](#).

**Note:** You can create a service account resource in an ALSB project only.

## Creating Service Key Provider Resources

In the ALSB perspective, select **File > New > Service Key Provider** to display the [New Service Key Provider Resource wizard](#).

**Note:** You can create a service key provider resource in an ALSB project only.

## Creating SMTP Server Resources

4. In the ALSB perspective, select **File > New > SMTP Server** to display the [New SMTP Server Resource wizard](#). Enter information as appropriate.

**Note:** You can create an SMTP server resource in an ALSB configuration project only.

## Creating XQuery Transformations

In the ALSB perspective, select **File > New > XQuery Transformation** to display the [XQuery/XSLT Expression Editor](#). Enter information as appropriate.

**Note:** You can create an XQuery transformation resource in an ALSB project only.

## Creating XSL Transformations

In the ALSB perspective, select **File > New > XSL Transformation** to display the [XPath Expression Editor](#).

**Note:** You can create an XSL transformation resource in an ALSB project only.

# Working with Business Services

The following topics describe how to create and work with business services in the ALSB plug-in.

- [Creating Business Services](#)
- [Editing Business Services](#)

## Creating Business Services

In the ALSB perspective, select **File > New > Business Service** to display the New AquaLogic Business Service wizard. See:

- [Business Service General Configuration page](#)
- [Business Service Message Type Configuration page](#)
- [Business Service Service Policy Configuration page](#)
- [Business Service SOAP Binding Configuration page](#)
- [Business Service Transport Configuration page](#)

**Note:** You can create a business service in an ALSB project only.

## Editing Business Services

1. In the Project Explorer, find the business service you want to edit.
2. Double-click the name of the service.
3. Select the page containing the options you want to edit, and make changes as appropriate. See:
  - [Business Service General Configuration page](#)
  - [Business Service Message Type Configuration page](#)
  - [Business Service Service Policy Configuration page](#)
  - [Business Service SOAP Binding Configuration page](#)
  - [Business Service Transport Configuration page](#)

## Working with Proxy Services

The following topics describe how to create and work with proxy services in the ALSB plug-in.

- [Creating Proxy Services](#)
- [Editing Proxy Services](#)

## Creating Proxy Services

In the ALSB perspective, select **File > New > Proxy Service** to display the New AquaLogic Proxy Service wizard. See:

- [Proxy Service General Configuration page](#)
- [Proxy Service Message Level Security Configuration page](#)
- [Proxy Service Message Type Configuration page](#)
- [Proxy Service Operation Selection Configuration page](#)
- [Proxy Service Service Policy Configuration page](#)
- [Proxy Service SOAP Binding Configuration page](#)
- [Proxy Service Transport Configuration page](#)

**Note:** You can create a proxy service in an ALSB project only.

## Editing Proxy Services

1. In the Project Explorer, find the proxy service you want to edit.
2. Double-click the name of the service.
3. Select the page containing the options you want to edit, and make changes as appropriate. See:
  - [Proxy Service General Configuration page](#)
  - [Proxy Service Message Level Security Configuration page](#)
  - [Proxy Service Message Type Configuration page](#)
  - [Proxy Service Operation Selection Configuration page](#)
  - [Proxy Service Service Policy Configuration page](#)
  - [Proxy Service SOAP Binding Configuration page](#)
  - [Proxy Service Transport Configuration page](#)

## Working with Alert Destinations

The following topics describe how to create and work with alert destinations in the ALSB plug-in.

- [Creating Alert Destinations](#)
- [Editing Alert Destinations](#)
- [Adding E-mail Recipients to Alert Destinations](#)
- [Adding JMS Destinations to Alert Destinations](#)

## Creating Alert Destinations

1. In the Project Explorer in the ALSB perspective, right-click a project or folder in which you want to create an alert destination.
2. From the menu, select **File > New > Alert Destination** to display the New Alert Destination Resource wizard. Enter information as appropriate. See [Alert Destination editor](#).

**Note:** You can create an alert destination in an ALSB project only.

## Editing Alert Destinations

1. In the Project Explorer, find the project folder containing the alert destination you want to edit.
2. Double-click the name of the alert destination to display the [Alert Destination editor](#). Edit information, as desired.

## Adding E-mail Recipients to Alert Destinations

1. Create or edit an alert destination, as described in [Creating Alert Destinations](#) and [Editing Alert Destinations](#).
2. In the **E-mail Recipients** field of the [Alert Destination editor](#), click **Add** to display the [Edit E-mail Recipient page](#). Add information, as appropriate.

## Adding JMS Destinations to Alert Destinations

1. Create or edit an alert destination, as described in [Creating Alert Destinations](#) and [Editing Alert Destinations](#).
2. In the **JMS Destinations** field of the [Alert Destination editor](#), click **Add** to display the [Edit JMS Destination page](#). Add information, as appropriate.

## Working with Proxy Service Message Flows

The following topics describe how to add and configure nodes and actions to proxy service message flows.

- [Constructing Proxy Service Message Flows](#)
- [Adding and Configuring Alert Actions in Message Flows](#)
- [Adding and Configuring Assign Actions in Message Flows](#)
- [Adding and Configuring Conditional Branch Nodes in Message Flows](#)
- [Adding and Configuring Dynamic Publish Actions in Message Flows](#)
- [Adding and Configuring Dynamic Routing Actions in Message Flows](#)
- [Adding and Configuring Error Handlers in Message Flows](#)
- [Adding and Configuring For-Each Actions in Message Flows](#)

## Tasks

- [Adding and Configuring If-Then Actions in Message Flows](#)
- [Adding and Configuring Insert Actions in Message Flows](#)
- [Adding and Configuring Java Callout Actions in Message Flows](#)
- [Adding and Configuring Log Actions in Message Flows](#)
- [Adding and Configuring MFL Transform Actions in Message Flows](#)
- [Adding and Configuring Operational Branch Nodes in Message Flows](#)
- [Adding and Configuring Pipeline Pair Nodes in Message Flows](#)
- [Adding and Configuring Publish Actions in Message Flows](#)
- [Adding and Configuring Publish Table Actions in Message Flows](#)
- [Adding and Configuring Raise Error Actions in Message Flows](#)
- [Adding and Configuring Rename Actions in Message Flows](#)
- [Adding and Configuring Replace Actions in Message Flows](#)
- [Adding and Configuring Report Actions in Message Flows](#)
- [Adding and Configuring Replace Actions in Message Flows](#)
- [Adding and Configuring Reply Actions in Message Flows](#)
- [Adding and Configuring Resume Actions in Message Flows](#)
- [Adding and Configuring Route Nodes in Message Flows](#)
- [Adding and Configuring Routing Actions in Message Flows](#)
- [Adding and Configuring Routing Options Actions in Message Flows](#)
- [Adding and Configuring Routing Table Actions in Message Flows](#)
- [Adding and Configuring Service Callout Actions in Message Flows](#)
- [Adding and Configuring Skip Actions in Message Flows](#)
- [Adding and Configuring Stages in Message Flows](#)
- [Adding and Configuring Transport Headers Actions in Message Flows](#)
- [Adding and Configuring Validate Actions in Message Flows](#)

## Constructing Proxy Service Message Flows

When you create a proxy service, a message flow is created by default, with an empty starting node. The process for constructing the message flow follows this general pattern:

1. Open the [Message Flow Editor](#) for the proxy service. To open the proxy service, double-click its name in Project Explorer. The Message Flow Editor appears as a tab in the proxy service view.
2. Open the [Message Flow Design Palette](#). To open the palette, in the ALSB perspective, select **Window > Show View > Design Palette**.
3. Open the Properties view, if it is not already open:
  - a. In the ALSB perspective, select **Window > Show View > Other**.
  - b. In the Show View dialog, select **General > Properties**.
4. Drag nodes and actions from the Message Flow Design Palette to the Message Flow Editor.

Alternatively, you can right-click a node or action in the Message Flow Editor to display menus of nodes and actions that can be inserted in that location. The menu contains one or more the following:

- **Insert > (list of nodes and actions)**
  - **Insert Into > (list of nodes and actions)**
  - **Insert After > (list of nodes and actions)**
  - **Add Error Handler**
5. Configure nodes and actions:
    - a. In the Proxy Service Editor, select the node or action by clicking it.  
 Alternatively, you can select a node or an action from the Outline view. To open the Outline view, in the ALSB perspective, select **Window > Show View > Outline**.
    - b. In the Properties view, set the properties, as appropriate for the selected node or action. For instructions on how to configure the nodes and actions, click the Properties view for a node or action, and press F1 for help.

## Adding and Configuring Alert Actions in Message Flows

Use the alert action to generate alerts based on message context in a pipeline, to send to an alert destination.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add an alert action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Reporting** list, if it is not already open.
2. Drag the alert action to the desired location in the message flow.

### To configure the alert action

1. In the [Message Flow Editor](#), click the alert action, if it is not already selected.
2. On the [Alert Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Assign Actions in Message Flows

Use an assign action to assign the result of an XQuery expression to a context variable.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add an assign action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Message Processing** list, if it is not already open.
2. Drag the assign action to the desired location in the message flow.

### To configure the assign action

1. In the [Message Flow Editor](#), click the assign action, if it is not already selected.
2. On the [Assign Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Conditional Branch Nodes in Message Flows

Use a conditional branch node to specify that message processing is to proceed along exactly one of several possible paths, based on a result returned by an XPath condition.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

#### **To add a conditional branch node**

1. In the [Message Flow Design Palette](#), open the **ALSB Message Flow > Nodes** list, if it is not already open.
2. Drag the conditional branch node to the desired location in the message flow.

#### **To configure the conditional branch node**

1. In the [Message Flow Editor](#), click the conditional branch node, if it is not already selected.
2. On the [Conditional Branch Node Properties](#) page, edit properties as appropriate.x

## **Adding and Configuring Delete Actions in Message Flows**

Use a delete action to delete a context variable or a set of nodes specified by an XPath expression.

#### **Before you begin**

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

#### **To add a delete action**

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Message Processing** list, if it is not already open.
2. Drag the delete action to the desired location in a stage action in the message flow.

#### **To configure the delete action**

1. In the [Message Flow Editor](#), click the delete action, if it is not already selected.
2. On the [Delete Action Properties](#) page, edit properties as appropriate.

## **Adding and Configuring Dynamic Publish Actions in Message Flows**

Use a dynamic publish action to publish a message to a service specified by an XQuery expression.

#### **Before you begin**

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

#### **To add a dynamic publish action**

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Communication** list, if it is not already open.
2. Drag the dynamic publish action to the desired location in the message flow.

#### **To configure the dynamic publish action**

1. In the [Message Flow Editor](#), click the dynamic publish action, if it is not already selected.
2. On the [Dynamic Publish Action Properties](#) page, edit properties as appropriate.

## **Adding and Configuring Dynamic Routing Actions in Message Flows**

Use a dynamic routing action to assign a route for a message based on routing information available in an XQuery resource.

#### **Before you begin**

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

#### **To add a dynamic routing action**

1. In the [Message Flow Design Palette](#), open the **Route Actions > Communication** list, if it is not already open.
2. Drag the dynamic routing action to the route action in the message flow.

#### **To configure the dynamic routing action**

1. In the [Message Flow Editor](#), click the dynamic routing action, if it is not already selected.
2. On the [Dynamic Routing Action Properties](#) page, edit properties as appropriate.

## **Adding and Configuring Error Handlers in Message Flows**

Use an error handler to specify what should happen if an error occurs in a specific location in the message flow.

#### **Before you begin**

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

#### **To add an error handler**

1. In the [Message Flow Design Palette](#), open the **ALSB Message Flow > Nodes** list, if it is not already open.
2. Drag the error handler to the desired location in the message flow.
3. Drag a stage node to the error handler.
4. Add actions to the stage, as appropriate, to define the error handler.

#### **To configure the error handler**

1. In the [Message Flow Editor](#), click the error handler, if it is not already selected.
2. On the [Error Handler Node Properties](#) page, edit the properties.
3. Click the stage node, if it is not already selected.
4. On the [Stage Node Properties](#) page, edit the properties.
5. Select and edit any actions contained by the stage, as appropriate.

## **Adding and Configuring For-Each Actions in Message Flows**

Use the for-each action to iterate over a sequence of values and execute a block of actions.

#### **Before you begin**

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

#### **To add a for-each action**

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Flow Control** list, if it is not already open.
2. Drag the for-each action to the desired stage action in the message flow.

#### **To configure the for-each action**

1. In the [Message Flow Editor](#), click the for-each action, if it is not already selected.
2. On the [For-Each Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring If-Then Actions in Message Flows

Use an if-then action to perform an action or a set of actions conditionally, based on the Boolean result of an XQuery expression.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add an if-then action

1. In the [Message Flow Design Palette](#), do one of the following:
  - For an if-then action in a route node, open the **Route Actions > Flow Control** list, if it is not already open.
  - For an if-then action in a stage node, open the **Stage Actions > Flow Control** list, if it is not already open.
2. Drag the if-then action to the route node or to the desired stage action in the message flow.

### To configure the if-then action

1. In the [Message Flow Editor](#), click each if condition and else-if condition contained by the if-then action, and define the conditions in the [Condition Editor](#), as described in [If-Then Action Properties](#).

## Adding and Configuring Insert Actions in Message Flows

Use an insert action to insert the result of an XQuery expression at an identified place relative to nodes selected by an XPath expression.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add an insert action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Message Processing** list, if it is not already open.
2. Drag the insert action to the desired location in the message flow.

### To configure the insert action

1. In the [Message Flow Editor](#), click the insert action, if it is not already selected.
2. On the [Insert Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Java Callout Actions in Message Flows

Use a Java callout action to invoke a Java method or an EJB business service from within the message flow.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add an Java callout action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Message Processing** list, if it is not already open.
2. Drag the Java callout action to the desired location in the message flow.

### To configure the Java callout action

1. In the [Message Flow Editor](#), click the Java callout action, if it is not already selected.
2. On the [Java Callout Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Log Actions in Message Flows

Use the log action to construct a message to be logged and to define a set of attributes with which it will be logged.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a log action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Reporting** list, if it is not already open.
2. Drag the log action to the desired location in the message flow.

### To configure the log action

1. In the [Message Flow Editor](#), click the log action, if it is not already selected.
2. On the [Log Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring MFL Transform Actions in Message Flows

Use a MFL (Message Format Language) transform action to convert message content from XML to non-XML, or vice versa, in the message pipeline.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a MFL transform action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Message Processing** list, if it is not already open.
2. Drag the MFL transform action to the desired location in the message flow.

### To configure the MFL transform action

1. In the [Message Flow Editor](#), click the MFL transform action, if it is not already selected.
2. On the [MFL Transform Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Operational Branch Nodes in Message Flows

Use an operational branch node to configure branching based on operations defined in a WSDL.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add an operational branch node

1. In the [Message Flow Design Palette](#), open the **ALSB Message Flow > Nodes** list, if it is not already open.
2. Drag the operational branch node to the desired location in the message flow.

### To configure the operational branch node

1. In the [Message Flow Editor](#), click the operational branch node, if it is not already selected.
2. On the [Operational Branch Node Properties](#) page, edit properties as appropriate.

## Adding and Configuring Pipeline Pair Nodes in Message Flows

Use a pipeline pair node to define request and response processing.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a pipeline pair node

1. In the [Message Flow Design Palette](#), open the **ALSB Message Flow > Nodes** list, if it is not already open.
2. Drag the pipeline pair node to the desired location in the message flow.

### To configure the pipeline pair node

1. In the [Message Flow Editor](#), click the pipeline pair node, if it is not already selected.
2. On the [Pipeline Pair Node Properties](#) page, edit properties as appropriate.

## Adding and Configuring Publish Actions in Message Flows

Use a publish action to identify a statically specified target service for a message and to configure how the message is packaged and sent to that service.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a publish action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Communication** list, if it is not already open.
2. Drag the publish action to the desired location in the message flow.

### To configure the publish action

1. In the [Message Flow Editor](#), click the publish action, if it is not already selected.

2. On the [Publish Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Publish Table Actions in Message Flows

Use a publish table action to publish a message to zero or more statically specified services.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a publish table action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Communication** list, if it is not already open.
2. Drag the publish table action to the desired location in the message flow.

### To configure the publish table action

1. In the [Message Flow Editor](#), click the publish table action, if it is not already selected.
2. On the [Publish Table Action Properties](#) page, click **<Expression>** to display the [XQuery/XSLT Expression Editor](#). Create an XQuery expression, which at run time returns the value upon which the routing decision will be made.
3. In the Message Flow Editor, select a case action.
4. From the **Operator** list on the Publish Table Action Properties page, select a comparison operator. Then, in the **Value** field, enter a value against which the value returned from the XQuery expression will be evaluated.
5. In the Message Flow Editor, click one of the publish table's publish actions to select it.
6. On the [Publish Action Properties](#) page, click **Browse** to select a service. Select the service to which messages are to be published if the expression evaluates true for the value you specified. The **Select a Service Resource** dialog is displayed.
7. Select a service from the list, then click **OK**. This is the target service for the message.
8. If the service has operations defined, you can specify the operation to be invoked by selecting it from the **invoking** list.
9. If you want the outbound operation to be the same as the inbound operation, select the **Use inbound operation for outbound** check box.

10. In the **Request Actions** field, to configure how the message is packaged and sent to the service, click **Add an Action**, then select one or more actions that you want to associate with the service. To learn more about the type of action you want to add, see [“Adding and Editing Actions in Message Flows” on page 18-1](#).

**Note:** There is a nesting limit of four cumulative levels in the stage editor. If you attempt to add a fifth level, nesting action is not displayed. Cumulative levels include all branching actions: if... then... conditions, publish tables, and route tables. For example, you can have 2 levels of conditionals, then a publish table with a route table inside of it, bringing the total to 4 levels. If you attempt to add another conditional (to the last publish table), the conditional is not displayed.

11. To insert a new case, click the  **Case** icon, then select **Insert New Case**.
12. Repeat steps 4-8 for the new case.
13. Add additional cases as dictated by your business logic.
14. Click the  **Case** icon of the last case you define in the sequence, then select **Insert Default Case** to add a default case at the end.
15. Configure the default case—the configuration of this case specifies the routing behavior in the event that none of the preceding cases is satisfied.

## Adding and Configuring Raise Error Actions in Message Flows

Use the raise error action to raise an exception with a specified error code (a string) and description.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a raise error action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Flow Control** list, if it is not already open.
2. Drag the raise error action to the desired location in the message flow.

### To configure the raise error action

1. In the [Message Flow Editor](#), click the raise error action, if it is not already selected.
2. On the [Raise Error Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Rename Actions in Message Flows

Use the rename action to rename elements selected by an XPath expression without modifying the contents of the element.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add an rename action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Message Processing** list, if it is not already open.
2. Drag the rename action to the desired location in the message flow.

### To configure the rename action

1. In the [Message Flow Editor](#), click the rename action, if it is not already selected.
2. On the [Rename Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Replace Actions in Message Flows

Use a replace action to replace a node or the contents of a node specified by an XPath expression. The node or its contents are replaced with the value returned by an XQuery expression.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a replace action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Message Processing** list, if it is not already open.
2. Drag the replace action to the desired location in the message flow.

### To configure the replace action

1. In the [Message Flow Editor](#), click the replace action, if it is not already selected.

2. On the [Replace Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Reply Actions in Message Flows

Use the reply action to specify that an immediate reply be sent to the invoker.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a reply action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Flow Control** list, if it is not already open.
2. Drag the reply action to the desired location in the message flow.

### To configure the reply action

1. In the [Message Flow Editor](#), click the reply action, if it is not already selected.
2. On the [Reply Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Report Actions in Message Flows

Use the report action to enable message reporting for a proxy service.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a report action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Reporting** list, if it is not already open.
2. Drag the report action to the desired location in the message flow.

### To configure the report action

1. In the [Message Flow Editor](#), click the report action, if it is not already selected.
2. On the [Report Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Resume Actions in Message Flows

Use the resume action to resume message flow after an error is handled by an error handler. This action has no parameters and can only be used in error pipelines.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a resume action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Flow Control** list, if it is not already open.
2. Drag the resume action to the desired location in the message flow.

### To configure the resume action

1. In the [Message Flow Editor](#), click the resume action, if it is not already selected.
2. On the [Resume Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Route Nodes in Message Flows

Use the route node to handle request and response dispatching of messages to and from business services.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a route node

1. In the [Message Flow Design Palette](#), open the **ALSB Message Flow > Nodes** list, if it is not already open.
2. Drag the route node to the desired location in the message flow.

### To configure the route node

1. In the [Message Flow Editor](#), click the route node action, if it is not already selected.
2. On the [Route Node Properties](#) page, edit properties as appropriate.

## Adding and Configuring Routing Actions in Message Flows

Use a routing action to identify a target service for the message and configure how the message is routed to that service.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a routing action

1. In the [Message Flow Design Palette](#), open the **Route Actions > Communication** list, if it is not already open.
2. Drag the routing action to the desired location in the message flow.

### To configure the routing action

1. In the [Message Flow Editor](#), click the routing action, if it is not already selected.
2. On the [Routing Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Routing Options Actions in Message Flows

Use a routing options action to modify any or all of the following properties in the outbound request: URI, Quality of Service, Mode, Retry parameters, Message Priority.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a routing options action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Communication** list, if it is not already open.
2. Drag the routing options action to the desired location in the message flow.

### To configure the routing options action

1. In the [Message Flow Editor](#), click the routing options action, if it is not already selected.
2. On the [Routing Options Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Routing Table Actions in Message Flows

Use a routing table to select different routes based upon the results of a single XQuery expression. A routing table action contains a set of routes wrapped in a switch-style condition table.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a routing table action

1. In the [Message Flow Design Palette](#), open the **Route Actions > Communication** list, if it is not already open.
2. Drag the routing table action to the desired location in the message flow.

### To configure the routing table action

1. In the [Message Flow Editor](#), click the routing table action, if it is not already selected.
2. On the [Routing Table Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Service Callout Actions in Message Flows

Use a service callout action to configure a synchronous (blocking) callout to an ALSB-registered proxy or business service.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a service callout action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Communication** list, if it is not already open.
2. Drag the service callout action to the desired location in the message flow.

### To configure the service callout action

1. In the [Message Flow Editor](#), click the service callout action, if it is not already selected.

2. On the [Service Callout Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Skip Actions in Message Flows

Use the skip action to specify that at run time, the execution of the current stage is skipped and the processing proceeds to the next stage in the message flow.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a skip action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Flow Control** list, if it is not already open.
2. Drag the skip action to the desired location in the message flow.

### To configure the skip action

1. In the [Message Flow Editor](#), click the skip action, if it is not already selected.
2. On the [Skip Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Stages in Message Flows

Use a stage node as a container for actions in a message flow.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a stage

1. In the [Message Flow Design Palette](#), open the **ALSB Message Flow > Nodes** list, if it is not already open.
2. Drag the stage to the desired location in the message flow.
3. Add actions to the stage, as appropriate for your configuration.

### To configure the stage

1. In the [Message Flow Editor](#), click the stage, if it is not already selected.

2. On the [Stage Node Properties](#) page, edit properties as appropriate.

## Adding and Configuring Transport Headers Actions in Message Flows

Use a transport header action to set header values in messages.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a transport headers action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Communication** list, if it is not already open.
2. Drag the transport headers action to the desired location in the message flow.

### To configure the transport headers action

1. In the [Message Flow Editor](#), click the transport headers action, if it is not already selected.
2. On the [Transport Headers Action Properties](#) page, edit properties as appropriate.

## Adding and Configuring Validate Actions in Message Flows

Use a validate action to validate elements selected by an XPath expression against an XML schema element or a WSDL resource.

### Before you begin

Display the message flow for the desired proxy service. See [Constructing Proxy Service Message Flows](#).

### To add a validate action

1. In the [Message Flow Design Palette](#), open the **Stage Actions > Message Processing** list, if it is not already open.
2. Drag the validate action to the desired location in the message flow.

### To configure the validate action

1. In the [Message Flow Editor](#), click the validate action, if it is not already selected.
2. On the [Validate Action Properties](#) page, edit properties as appropriate.

## Working with MQ Connections

MQ connections are sharable resources that can be reused across multiple MQ proxy and business services. MQ proxy and business services must connect to a MQ queue manager before accessing an MQ queue. MQ Connection resources provide the connection required for connecting to an MQ queue manager.

Each MQ Connection resource has a connection pool. Every business or proxy service using a given MQ Connection resource to get a connection to a given queue manager uses the same connection pool that was created for that resource. Thus, multiple business services and proxy services using the same queue manager share a connection pool.

To learn more about ALSB MQ Connection resources and native MQ transports, see the *Native MQ Transport User Guide*.

To learn more about WebSphere MQ Fundamentals, see <http://www.redbooks.ibm.com/redbooks/SG247128/wwhelp/wwhimpl/java/html/wwhelp.htm>.

## Adding MQ Connections

In ALSB, MQ connections are created as custom resources. Therefore, to add an MQ connection, you must create it as a custom resource, as follows:

1. In the ALSB perspective, select **File > New > Custom Resource** to display [New Custom Resource wizard](#).
2. On the Create a New Custom Resource page, in the **Resource Type** field, select **MQ Connection**.
3. Enter configuration information, as appropriate, on the [Custom MQ Resource Configuration page](#).

## Editing MQ Connections

1. In the Project Explorer, find the ALSB configuration folder containing the MQ connection resource you want to edit.
2. Double-click the name of the MQ connection to display the [Custom MQ Resource Configuration page](#). Edit as appropriate.

## Working with UDDI Registries

Universal Description, Discovery and Integration (UDDI) registries are used in an enterprise to share Web Services. UDDI provides a framework in which to classify your business, its services, and the technical details about the services you want to expose.

Publishing a service to a registry requires knowledge of the service type and the data structure representing that service in the registry. A registry entry has certain properties associated with it and these property types are defined when the registry is created. You can publish your service to a registry and make it available for other organizations to discover and use. Proxy services developed in ALSB can be published to a UDDI registry. ALSB can interact with any UDDI version 3.0-compliant registry.

See also [UDDI](#) in the *AquaLogic Service Bus User Guide*.

## Adding UDDI Registries

1. In the ALSB perspective, select **File > New > UDDI Registry**. to display the New UDDI Resource wizard.

**Note:** You can add a UDDI registry only to an ALSB configuration project only.

2. After choosing a location and entering a name, configure the registry on the [UDDI Registry Configuration page](#).

**Note:** You can add a UDDI registry in an ALSB configuration project only.

## Configuring UDDI Registries

1. In the Project Explorer, find the UDDI registry you want to configure.
2. Double-click the name of the registry.
3. Set configure options on the [UDDI Registry Configuration page](#).

## Importing Business Services From a UDDI Registry

1. Create a business service, as described in “[Creating Business Services](#)” on page 2-6.
2. In the New AquaLogic Business Service wizard [Business Service General Configuration page](#), select **WSDL Web Service**. then click **Browse**.
3. In the Select a WSDL dialog, click **Consume**.

4. In the Service Consumption dialog, select **UDDI**.

For help using UDDI Register Access in the Service Consumption dialog, press F1, or search in the help system for “Service Consumption dialog.”

## Working with Split-Join

This section provides instructions for creating and configuring Split-Joins. Following are the primary topics in this section:

- [Introduction to Split-Join](#)
- [Designing a Split-Join](#)
- [Designing a Static Split-Join](#)
- [Designing a Dynamic Split-Join](#)

## Introduction to Split-Join

The Split-Join is a mediation pattern that can be used by a transport typed business service in an ALSB message flow. Split-Join allows you to send message requests to multiple services concurrently, thus enhancing performance in comparison to sending them sequentially. Split-Join achieves this task by splitting an input message into individual messages, routing them concurrently to their destinations, and then aggregating the responses into one overall message.

You design a Split-Join in the WorkSpace Studio Split-Join editor, then export it to the ALSB console for testing and production.

**Note:** In the ALSB console, a Split-Join is associated with a business service using the Flow transport protocol. Therefore, the Split-Join has a .flow file name extension in WorkSpace Studio even though it is always referred to simply as a “Split-Join” in this document.

There are two types of Split-Join pattern: static Split-Join and dynamic Split-Join, as described in [Designing a Split-Join](#).

For more information on invoking a business service from an ALSB message flow, see [Proxy Services: Message Flow](#) in the ALSB console help system.

## Designing a Split-Join

There are two Split-Join patterns, the Static Split-Join and the Dynamic Split Join.

The Static Split-Join can be used to create a fixed number of message requests (as opposed to an unknown number). For instance, a customer places an order for a cable package that includes three separate services: internet service, TV service, and telephone service. In the Static use case, you could execute all three requests in separate parallel branches to improve performance time over the standard sequential execution.

The Dynamic Split-Join can be used to create a variable number of message requests. For instance, a retailer places a batch order containing a variable number of individual purchase orders. In the Dynamic use case, you could parse the batch order and create a separate message request for each purchase. Like the Static use case, these messages can then be executed in parallel for improved performance.

## Initial Setup

Split-Joins potentially include the following tasks as part of their initial setup:

### Creating/Importing a WSDL Containing the Base Operation

Every Split-Join is based upon a WSDL operation. When you first create a Split-Join, you will be asked to browse to the appropriate WSDL file and to select this operation as part of the creation process. You can create this WSDL file in WorkSpace Studio.

### Creating/Importing a Business Service to Use the Split-Join

Every Split-Join will be used by a transport typed business service, which, in turn, is invoked by a proxy service. You cannot export or test your Split-Join until you have created this business service. If it already exists, you can import it into WorkSpace Studio, or, if it does not exist, you can create it in WorkSpace Studio or the ALSB console. If you want to get started on your Split-Join before you create the business service, you can generate the business service automatically after you create the Split-Join.

## Designing a Static Split-Join

Suppose you want to design a new Split-Join called *Service Availability* that handles orders for a telco's cable service package including TV, phone, and internet service. The idea is for the Split-Join to receive an incoming package order and to reply with an order acknowledgement for each type of service. In this case, *Service Availability* is designed as a *Static* Split-Join because there are three message requests per order, one for each type of service. In this particular example the customer requests only TV and DSL service.


Creating the *Service Availability* Split-Join may include the following tasks:

1. Creating a New Split-Join
2. Adding an Assign
3. Adding a Parallel Node
4. Adding an Assign for Each Branch
5. Adding an Invoke External Service
6. Adding an Assign for Each Branch
7. Exporting and Testing the Split-Join

## 1. Creating a New Split-Join

Create a new Split Join based on the WSDL operation you want to use for placing the order. In this case the WSDL operation we want is called “telecom.”

After you select the WSDL operation, a skeleton of the newly created Split-Join appears in the Split-Join editor, as shown in the following figure. It consists of a Start Node, a Receive, a Reply. The labels are then edited in the general properties tab to better reflect the specific function of each node in this particular Split-Join.



The Start Node contains both a Request Variable and a Response Variable that have been determined by the WSDL operation initially selected. The Receive receives the incoming request message (in this case for the three or fewer different kinds of cable service), and the Reply generates a response message and sends it back to the client.

**Note:** The Receive node requires no further configuration. Similarly the Reply requires no further configuration, unless to generate an error fault--which is not the case in this scenario (see [Configuring a Reply](#) for more information on generating faults).


## 2. Adding an Assign

The first Assign, *Prepare Output Message*, contains an Assign operation that prepares the Response Variable in a form such that the later nodes can work on the data within it (that is, Copy/Insert/Assign/Replace/Delete the data). This output message is relayed to the final Reply node in the Split-Join and, in turn, returned to the original client.




## 3. Adding a Parallel Node

The Parallel Node contains two main branches, one to check cable TV availability and one to check DSL availability. Each branch is composed of a number of actions, the sequence and general configuration being the same for both branches.



#### 4. Adding an Assign for Each Branch

The first Assign in each Parallel Branch, Prepare Input Address, copies the incoming customer address data into a Variable that is referenced to check the availability of the service at that location. The Assigns are the same for each branch and would be for additional branches as well.




## 5. Adding an Invoke External Service

An External Service is then invoked to check whether the requested service type is available at the customer's location. Each branch contains one Invoke External Service, *Check Cable TV Availability* and *Check DSL Availability*. Each invocation calls an External Service, which compares the customer's address (stored in the Variable initialized in the previous step) to the availability of the service at that location. The result is then stored in an output Variable that is passed on to the final Assign in the Branch below.

## 6. Adding an Assign for Each Branch

The final two Assigns, *Update Cable TV Status in Output Message* and *Update DSL Status in Output Message*, take the results of the external service invocations and put them into the output message using a Replace operation. The aggregated response are then sent to the original client in the final Reply node, which requires no further configuration.



## 7. Exporting and Testing the Split-Join

After you design the Split-Join, you can export it to the ALSB console for testing and production.



### Related Topics

- [Creating a New Split-Join](#)
- [Configuring the Start Node](#)
- [Creating an Assign](#)
- [Creating an Invoking External Service](#)
- [Creating a Parallel](#)

- [Exporting and Testing a Split-Join](#)

## Designing a Dynamic Split-Join

Suppose that you want to design a Split-Join that handles a batch order from a retailer containing a variable number of individual purchase orders (as opposed to a fixed number of orders). The idea is for the Split-Join to receive the batch order and to reply with an order acknowledgement for each order within. This would be a *Dynamic* Split-Join because the number of individual purchase order requests is variable and unknown at design time.


Creating this Split-Join may include the following tasks:

1. [Creating a New Split-Join](#)
2. [Adding an Assign](#)
3. [Adding a For Each](#)
4. [Adding an Assign](#)
5. [Adding an Invoke External Service](#)
6. [Adding an Assign](#)
7. [Adding an Error Handler](#)
8. [Exporting and Testing the Split-Join](#)

### 1. Creating a New Split-Join

Create a new Split Join based off of the WSDL operation you want to use for placing the order. In this case the WSDL operation we want is called “batchOrders.”

After the operation is selected, a skeleton of the newly created Split-Join appears in the Split-Join editor consisting of a Start Node, a Receive, a Reply. The labels are then edited in the general properties tab to better reflect the specific function of each node in this particular Split-Join.




The Start Node, *Order Placement*, contains both a request variable, *inputVar*, and an response variable, *outputVar*. The Receive, *Receive Batch Order Request*, will initialize the contents of the Request Variable (in this case purchase orders), and the Reply, *Reply Order Placement*, will send a response, based on the order acknowledgements aggregated into the Response Variable, back to the client. In this example *Order Placement* also contains a callout to an External Service, “Order” that will be invoked to approve individual orders.

**Note:** The Receive node requires no further configuration. Similarly, the Reply requires no further configuration, unless you would like to generate an error fault—which is not the case in this scenario (see [Configuring a Reply](#) for more information on generating faults).


## 2. Adding an Assign

The first Assign, *Prepare Output Message*, contains an Assign operation that prepares the response variable (here labeled an “Output Message” for readability) in a form such that the later nodes can work on the data captured within it (that is, Copy/Insert/Assign/Replace/Delete into the Variable). In this case, that data would consist of order acknowledgements and/or errors. This Output Message is relayed to the final Reply node in the Split-Join and, in turn, returned to the original client.




### 3. Adding a For Each

The For Each, *Iterate Through Orders*, contains logic that will parse through each order in the batch, send it to an external proxy for approval, and capture an order acknowledgment in response. If there is a problem with an order, an error is sent from the invoked proxy and captured in the Error Handler. The following figure depicts the entire scope of the For Each logic.



#### 4. Adding an Assign

The Assign, *Prepare Purchase Order*, copies the incoming purchase order requests into a variable that is referenced to check approval of the order in the next step.



## 5. Adding an Invoke External Service

An external service, *Check Order Availability*, is then invoked to approve each individual purchase order. If the order is accepted, the service responds with an order acknowledgment. If the order is not accepted, the service responds with an error. The result is then stored in an output variable that is passed on to the final Assign in the next step.

## 6. Adding an Assign

The final Assign, *Update Order Status in Output Message*, takes the results of the external service invocation and copies them into the output message using an Insert operation. The aggregated response is then sent to the original client in the final Reply node, which requires no further configuration.



## 7. Adding an Error Handler


The Error Handler captures any Errors returned by the invoked service. It takes these errors and inserts them into the output message using an Assign operation.



## 8. Exporting and Testing the Split-Join

After you design the Split-Join, you can export it to the ALSB console for testing and production.

## Tasks



### Related Topics

- [Creating a New Split-Join](#)
- [Configuring the Start Node](#)
- [Creating an Error Handler](#)
- [Creating a Parallel](#)
- [Configuring a Reply](#)

- [Exporting and Testing a Split-Join](#)

## Creating a New Split-Join

In order to create a new Split/Join, you must have access to a WSDL containing the operation upon which to base the Split-Join. The Split Join must be created in an existing ALSB project within an existing ALSB configuration project.

To create a new Split-Join:

1. In the ALSB perspective, select **File > New > Split-Join**. This opens the New Split-Join Wizard.
2. In the New Split-Join Wizard, type or select an ALSB project location and enter a file name for the new Split-Join. When you have finished, click Next.
3. In the next screen, you must select a binding and then an operation on which to implement the Split-Join. There are two ways to make your selection:
  - a. Choose your operation from one of the WSDLs displayed in the Select Operation tree. All of the WSDLs in your current ALSB configuration project are available.
  - b. Import your WSDL into the ALSB configuration project using the Consume button. Consumption imports a new WSDL into your configuration from an outside source, as described in the following step.
4. If you choose to consume the base WSDL, go through the following steps:
  - a. Click **Consume**.
  - b. Browse for the location, or “Artifact Folder,” wherein you wish to generate the consumed WSDL. The default artifact folder is your current ALSB project.
  - c. If you want to overwrite existing local files, select the checkbox.
  - d. Choose the service resource in which the WSDL to be consumed resides: Enterprise Repository, File System, UDDI, URI, or Workspace.
  - e. Select The WSDL that you want to consume from that Service Resource. After you have made your selection the workspace will rebuild momentarily and the Service Consumption Status dialog will appear depicting the status of your consume. If it was successful, click **OK** to close the dialog.
  - f. The consumed WSDL is now in your ALSB configuration project, and you can select an operation from it upon which to base your Split-Join.

5. Click **Finish**.

A basic Split-Join is created and visually represented as a diagram in the Design View. By default, it consists of a Start Node, a Receive, and a Reply. The Start Node contains the Request and Response Variables introspected from the WSDL operation. The Receive is used to receive incoming request messages. The Reply is used to send response messages.

### Related Topics

- [Configuring the Start Node](#)
- [Configuring a Receive](#)
- [Creating a Parallel](#)
- [Split-Join Wizard - New Split Join](#)

## Configuring the Start Node

The Start Node is generated automatically whenever you create a new Split-Join. It is the starting point from which all the other nodes proceed. Configuring a Start Node can include the following tasks:

- Add General Information
- Define Global Variables
- View External Services

### Related Topics

- [Creating an Invoking External Service](#)
- [Split-Join Properties View - Start Node](#)

## Adding General Information

General information is useful for making a node more legible. It includes the ability to add a unique identifier, or Label, to the node and to supplement it with notes, or Documentation. General information is optional.

1. To add a Label to a node, open the Properties view and enter a unique, identifying string in the **Label** field. The label that you enter appears underneath the node in the Canvas Area. Alternatively, you can simply double-click the string under the icon and edit.

2. To add Documentation to a node, open the Properties view and enter any notes that you think are important in the **Documentation** field.

## Defining Global Variables

Variables in the Start Node store data that can be referenced globally, that is by any node in the Split-Join. By default, every Start Node is assigned both a request and a response variable when the Split-Join is initially created. From the Start Node, you can either create a new global variable or edit an existing global variable.

To create a new global variable:

1. Right-click the Start Node and select **Create Variable** to open the [Create Variable Dialog](#).
2. Enter a name for the variable.
3. Select the Variable Type (Builtin, Schema, or Message).
4. Choose a Variable.

**Note:** You may need to drill down into the hierarchy to select a Schema or Message Type variable.

5. Click **OK**.

If it is not already open, expand the content area to the left by clicking the arrow to the left of the Start Node icon. The newly created variable appears in the Variables field along with any other global variables. To view the details of any variable, simply select it and its structure will appear in the Properties view.

To edit an existing global Variable:

1. Open the Edit Variable Dialog in one of the following ways:
  - Right-click the selected variable and select **Edit Variable** from the context menu.
  - Select a variable and click **Edit** in the variable Properties view.
2. Enter a name for the Variable.
3. Select the Variable Type: Builtin, Schema, or Message.
4. Choose a variable.

**Note:** You may need to drill down into the hierarchy to select a Schema or Message Type variable.

5. Click **OK**.

If it is not already open, expand the content area to the left of the Start Node icon. The newly created variable appears in the Variables field along with any other global variables. To view the details of any variable, simply select it and its structure will appear in the Properties view.

## Viewing External Services

The External Services listed in the Start Node are those invoked outside of the context of the Split-Join. They are specified in an Invoke External Service but listed here for convenience.

To view External Services, expand the content area to the left of the Start Node by clicking the arrow to the left of the Start Node icon. When an External Service is selected, a dashed blue arrow appears pointing to the Invoke External Service associated with the service, and the service's location appears in the Properties view.

## Configuring a Receive

A Receive is generated automatically whenever you create a new Split-Join. The purpose of the Receive is to place incoming request data in a variable and make the contents available for later nodes to use. Configuring a Receive can include the following tasks:

- View the Operation
- Define the Receive Variable
- Add General Information

### Related Topics

- [Split-Join Properties View - Receive Page](#)

## Viewing the Operation

The Operation is based upon the initial WSDL selection for the overall Split-Join. It is displayed in the Properties View for reference.

## Defining the Receive Variable

You must define the Incoming Message Variable the Receive will initialize. This can be done in two ways:

1. Select a pre-existing variable from the Message Variable menu.

2. Create a new Message Variable (following steps).

**Note:** If there are no available Message Variables associated with the previously chosen Operation, you *must* create a new Message Variable.

To create a new Message Variable, select **Create Message Variable** from the Message Variable menu. The [Create Message Variable Dialog](#) appears:

1. Provide a name for the variable.
2. Click **OK**.

Note that Message Type Namespace and Message Type are displayed automatically on the Properties page once the variable is defined.

## Adding General Information

General information is useful for making a node more legible. It includes the ability to add a unique identifier, or Label, to the node and to supplement it with notes, or Documentation. General information is optional.

1. To add a Label to a node, open the Properties view and enter a unique, identifying string in the Label field. The label that you enter appears underneath the node in the Canvas area. Alternatively, you can simply double-click the string under the icon and edit.
2. To add Documentation to a node, open the Properties view and enter any notes that you think are important in the **Documentation** field.

## Creating an Assign

The Assign is used for data-manipulation including initializing and updating a variable. It is composed of a set of one or more operations that can be added and/or edited in the Assign toolbar. Configuring an Assign can include the following tasks:

- Add and Configure Assign Operations
- Add General Information

### Related Topics

- [Split-Join Properties View - Assign](#)

## Adding and Configuring Assign Operations

Assign operations include *Assign*, *Copy*, *Delete*, *Insert*, and *Replace*. Every Assign is composed of one or more of these operations, which you can add to the Assign using the Assign toolbar.

In addition, each operation has its own configuration dialog/editor.

**Note:** The Assign operations in the Split-Join editor are essentially the same as the corresponding actions in the WorkSpace Studio Message Flow editor. However, one important difference is that when you are using the XQuery\XSLT or XPath Editors to edit expressions in the Split-Join context, only variables and namespaces internal to the Split-Join are available.

A brief explanation of each operation follows:

- **Assign** the result of an XQuery Expression to a Variable.

For more information on configuring the Assign, see [Split-Join Properties View – Assign](#).

- **Copy** the information specified by an XPath 1.0 expression from a source document to a destination document. (This operation is unique to Split-Join and has no corresponding Action in the WorkSpace Studio Message Flow editor, as described in [Adding a Copy Operation](#)).

- **Delete** a set of nodes specified by an XPath expression.

**Note:** Unlike the ALSB delete, only an XPath expression may be deleted in a Split-Join, not the entire variable.

For more information on configuring the Delete operation, see [Delete Action Dialog](#).

- **Insert** the result of an XQuery Expression at an identified place relative to nodes selected by an XPath expression.

For more information on configuring the Insert operation, see [Insert Action Dialog](#).

- **Replace** a node or the contents of a node specified by an XPath expression

For more information on configuring the Replace operation, see [Replace Action Dialog](#).

Adding an operation to the Assign involves the following steps:

1. Select an operation from the Add Operation menu. The configuration dialog box for that expression appears.
2. Configure the operation.
3. Click **OK**.

4. Add and configure the next expression, if necessary.

Note that you can edit a configured operation by double-clicking the operation in the Assign Operations table or selecting an operation and clicking the Edit button in the toolbar.

## Adding a Copy Operation

The Copy operation allows you to copy the information specified by an XPath 1.0 expression from a source document to a destination document. It is an operation unique to the Split-Join editor. Adding a Copy operation to the Assign involves the following steps:

1. Select **Copy** from the Add operation menu. The Copy dialog box opens.
2. Select a **Copy From** type and a **Copy To** type.
3. If the type is an expression, enter the expression manually or click browse to launch the XQuery Expression Builder.
4. In the type is a variable, drill down to and select the desired element. The resulting query will be displayed in the Query field below.
5. If the Copy From type is a Literal, enter the literal in the text field.
6. If the Copy From type is an XML fragment, enter [or paste] the fragment in the text field.
7. Click **OK**.

## Adding General Information

General information is useful for making a node more legible. It includes the ability to add a unique identifier, or Label, to the node and to supplement it with notes, or Documentation. General information is optional.

1. To add a Label to a node, open the Properties view and enter a unique, identifying string in the **Label** field. The label that you enter appears underneath the node in the Canvas area. Alternatively, you can simply double-click the string under the icon and edit.
2. To add Documentation to a node, open the Properties view and enter any notes that you think are important in the **Documentation** field.

## Creating an Invoking External Service

The Invoke External Service is used to invoke external, WSDL-based business or proxy services. Configuring an Invoke Service can include the following tasks:

- Select an Operation
- Define Input and Output Variables
- Add General Information

### Related Topics

- [Configuring the Start Node](#)
- [About Scope](#)
- [Split-Join Properties View - Invoke External Service](#)

## Selecting an Operation

An operation must be selected upon which to base the Invoke External Service. You must select this operation before you can configure Input and Output variables. To select an operation:

1. Select the **Invoke External Service** for which you wish to select an operation and open the Properties view.
2. From the Operations tab in the Properties view, select **Browse** to launch the Service Browser.
3. In the Service Browser, drill down to the desired service and select a **Binding** and then an operation.
4. Click **OK**. The selected operation and its Service Location appear in the operation page.

**Note:** Clicking a selected Service Location will open the file.

## Defining Input and Output Variables

An Invoke External Service requires both an Input Variable and an Output Variable, unless it is a one-way invocation. The procedure to configure these variables is essentially the same. Either type of variable can be global (that is, available within the entire Split-Join) or local (that is, available within a particular context Scope.) To define either an Input or Output variable:

1. Define the Message Variable. This can be done in two ways:
  - a. Select a pre-existing variable from the Message Variable menu.
  - b. Create a new Message Variable (following steps).

**Note:** If there are no available Message Variables associated with the previously chosen operation, you *must* create a new Message Variable.

To create a new Message Variable:

1. Select **Create Message Variable** from the Message Variable menu. The [Create Message Variable Dialog](#) appears.
2. Provide a name for the variable.
3. Make the variable either global or local. Global variables are accessible within the entire Split-Join, whereas local variables are restricted to the current Scope.
4. Click **OK**.

Note that Message Type Namespace and Message Type are displayed automatically on the properties page once a variable is defined.

## Adding General Information

General information is useful for making a node more legible. It includes the ability to add a unique identifier, or Label, to the node and to supplement it with notes, or Documentation. General information is optional.

1. To add a Label to a node, open the Properties view and enter a unique, identifying string in the Label field. The Label that you enter appears underneath the node in the Canvas Area. Alternatively, you can simply double-click the string under the icon and edit.
2. To add Documentation to a node, open the Properties view and enter any notes that you think are important in the Documentation field.

## Creating a Parallel

The Parallel creates a fixed number of configured parallel branches. Each branch has its own Scope which in turn can contain any number of nodes. Configuring a Parallel can include the following tasks:


- Add Nodes
- Add General Information

### Related Topics

- [About Scope](#)
- 
- [Split-Join Properties View - Parallel](#)

## Adding Nodes

The Parallel is essentially a placeholder for a fixed number of processing branches, each with its own scope. Two branches are automatically generated by default. An individual scope may contain unique processing logic according to your construction; simply drag the appropriate nodes into the Scope. You may add additional branches with the Add Scope button.



## Adding General Information

General information is useful for making a node more legible. It includes the ability to add a unique identifier, or Label, to the node and to supplement it with notes, or Documentation. General information is optional.

1. To add a Label to a node, open the Properties view and enter a unique, identifying string in the **Label** field. The Label that you enter appears underneath the node in the Canvas area. Alternatively, you can simply double-click the string under the icon and edit.
2. To add Documentation to a node, open the Properties view and enter any notes that you think are important in the **Documentation** field.

## Creating a For Each

The For Each is used to create conditional logic for iterating through a variable number of requests. It is primarily used to create dynamic Split-Joins. Configuring a For Each can include the following tasks:

- Define the For Each Logic
- Add General Information

### Related Topics

- [Creating an Invoking External Service](#)

- [Creating an Invoking External Service](#)
- [Split-Join Properties View - For Each](#)

## Defining the For Each Logic

To define the For Each logic:

1. Set the Parallel property to yes or no. If you choose yes, individual branches will be processed in parallel. If you select no, they are processed sequentially.
2. Define the Counter Variable Name by clicking on the counter string.
3. Enter the **Start Counter Value**. If necessary, use the Browse button to create a new value in the XPath Expression Builder.

**Note:** The lowest possible starting counter value is “1.”

4. Enter the **Final Counter Value**. If necessary, use the Browse button to create a new value in the XPath Expression Builder.

**Note:** The lowest possible starting counter value is “1.”


## Adding General Information

General information is useful for making a node more legible. It includes the ability to add a unique identifier, or Label, to the node and to supplement it with notes, or Documentation. General information is optional.

1. To add a Label to a node, open the Properties view and enter a unique, identifying string in the **Label** field. The Label that you enter appears underneath the node in the Canvas area. Alternatively, you can simply double-click the string under the icon and edit.
2. To add Documentation to a node, open the Properties view and enter any notes that you think are important in the **Documentation** field.

## Creating an If Activity

The If Activity is used to provide conditional logic within a Split-Join. It is composed of a number of nodes that determine the behavior for the overall If activity. Each node must be individually configured. When you create an If activity, an If and an Else are automatically generated within it. You can add an unlimited number of Else If nodes with the Add Else If button.



Configuring an If Activity can include the following tasks:

- Configure the If
- Add and Configure Else If
- Configure the Else

### Related Topics

- [About Scope](#)
- [Designing a Dynamic Split-Join](#)
- [Split-Join Properties View - If Activity](#)

## Configuring the If

The If provides a unit of conditional logic within the overall If activity. It is automatically generated when you create an If activity. Configuring an If can include the following tasks:

- Write the logic of the condition
- Add resulting nodes
- Add General Information

### Related Topics

- [Split-Join Properties View – If and Else If](#)

## Writing the logic of the condition

The If Activity executes conditional logic defined by an XPath 1.0 expression. Enter this condition in the Condition text field of the Condition tab, or click the browse button to launch and write the expression in the Xpath 1.0 Expression Builder.

## Adding resulting nodes

If the condition in the If logic is met, a subsequent node or string of nodes will result. Add and configure any resulting nodes by dragging them in sequential order to a drop point beneath the If icon.


## Adding General Information

General information is useful for making a node more legible. It includes the ability to add a unique identifier, or Label, to the node and to supplement it with notes, or Documentation. General information is optional.

1. To add a Label to a node, open the Properties view and enter a unique, identifying string in the **Label** field. The Label that you enter appears underneath the node in the Canvas area. Alternatively, you can simply double-click the string under the icon and edit.
2. To add Documentation to a node, open the Properties view and enter any notes that you think are important in the **Documentation** field.

## Adding and Configuring Else If

The Else If is used to provide additional logic within the context of an overall If. You can add an Else If every time you press the “Add Else If” button.



Configuring an Else If can include the following tasks:

- Write the Logic of the Condition
- Add Resulting Nodes
- Add General Information

## Related Topics

- [Split-Join Properties View – If and Else If](#)

## Writing the Logic of the Condition

The Else If uses conditional logic defined by an XPath 1.0 expression. Enter this condition in the Condition text field of the Condition tab or click the browse button to launch and write the expression in the Xpath 1.0 Expression Builder.

## Adding Resulting Nodes

If the condition in the Else If logic is met, a subsequent node or string of nodes will result. Add and configure any resulting nodes by dragging them in sequential order to a drop point beneath the Else If icon.

## Adding General Information

General information is useful for making a node more legible. It includes the ability to add a unique identifier, or Label, to the node and to supplement it with notes, or Documentation. General information is optional.

1. To add a Label to a node, open the Properties view and enter a unique, identifying string in the **Label** field. The Label that you enter appears underneath the node icon in the Canvas area. Alternatively, you can simply double-click the string under the icon and edit.
2. To add Documentation to a node, open the Properties view and enter any notes that you think are important in the **Documentation** field.

## Configuring the Else

The Else provides a final case of logic within the context of an overall If. It is automatically generated when an If is created. Configuring an Else can include the following tasks:

- Add Resulting Nodes
- Add General Information

## Related Topics

- [Split-Join Properties View – If and Else If](#)

## Adding Resulting Nodes

As the final case in the If's logic, the Else requires no conditions to be met in order to execute. It will automatically execute resulting activities when invoked. Add and configure any resulting nodes by dragging them in sequential order to a drop point beneath the Else icon.

## Adding General Information

General information is useful for making a node more legible. It includes the ability to add a unique identifier, or Label, to the node and to supplement it with notes, or Documentation. General information is optional.

1. To add a Label to a node, open the Properties view and enter a unique, identifying string in the **Label** field. The Label that you enter appears underneath the node in the Canvas area. Alternatively, you can simply double-click the string under the icon and edit.
2. To add Documentation to a node, open the Properties view and enter any notes that you think are important in the **Documentation** field.

## Creating an Error Handler

The Error Handler receives and handles errors. If it is attached to a Start Node, it is a “global” Error Handler and serves as a catch-all for the output of all local Raise Error nodes. If it is attached to a Scope, it only handles errors raised locally. To create an Error Handler:

1. Select the node to which the Error Handler will be added.  
**Note:** It must be a Start Node or a Scope.
2. Right-click the selected icon and select **Add Error Handler**.
3. If you are invoking a SOAP Fault, in the Catch All tab of the Properties View, select **SOAP Fault Variable Name** to define a SOAP Fault variable associated with the Error Handler.

The basic Error Handler is now configured, but you may need to add additional Assign, If, and/or Reply nodes to it depending on whether you wish to execute logic upon the received faults before sending a response.

### Related Topics

- [Creating an Assign](#)
- [Creating an If Activity](#)
- [Creating a Parallel](#)
- [About Scope](#)
- [Split-Join Properties View - Error Handler](#)

## Creating a Raise Error

The Raise Error generates an error that causes the Split-Join to stop normal processing. If the error is not handled using an Error Handler, the Split-Join will terminate and a Fault will be sent to the ALSB message flow. Configuring a Raise Error can optionally include documenting the nature of the error in the General Information tab.

### Related Topics

- [Split-Join Properties View – Raise Error Page](#)

General information is useful for making a node more legible. It includes the ability to add a unique identifier, or Label, to the node and to supplement it with developer notes, or Documentation. General information is optional.

1. To add a Label to an node, open the Properties view and enter a unique, identifying string in the **Label** field. The Label that you enter appears underneath the node Icon in the Canvas area.
2. To add Documentation to an node, open the Properties view and enter any notes that you think are important in the **Documentation** field.

## Configuring a Reply

A global Reply is generated automatically whenever you create a new Split-Join. The purpose of the global Reply is to send a response back to the invoking ALSB message flow. However, you may also create a local Reply to an Error Handler. Configuring the Reply can include the following tasks:

- View the Operation
- Define the Reply Variable
- Add General Information

### Related Topics

- [Split-Join Properties View - Reply Page](#)

## Viewing the Operation

The operation is based upon the initial WSDL selection for the overall Split-Join. It is displayed in the Properties view for reference.

## Defining the Reply Variable

The Reply can either send a Response or a Fault back to the client depending on how you configure the variable. The Fault options available vary depending upon whether the Reply is global or local.

- A global Reply (that is, a Reply at the end of a Split-Join) can never have a SOAP Fault but can have a WSDL Fault. This is why the SOAP Fault option is always disabled.
- A local Reply (that is, a Reply attached to an Error Handler) can have either a WSDL Fault or a SOAP Fault. WSDL Faults will be available only if they were defined in the WSDL upon which the Split-Join is based. The SOAP Fault option will always be available provided one has been previously defined in the Error Handler.

**Note:** Switching back and forth between the Response and Fault buttons will clear either configuration. For instance, if you have previously selected “Propagate SOAP Fault” for Fault configuration and you then switch to the “Response” configuration, “Propagate SOAP Fault” will be deselected.

Given the available options as outlined above, select either a Response or a Fault for your Reply Variable.

If you select Response, you must define the Message Variable the Response will be assigned to. This can be done in two ways:

1. Select a pre-existing variable from the Message Variable menu.
2. Create a new Message Variable (following steps).

**Note:** If there are no available Message Variables associated with the previously chosen operation, you *must* create a new Message Variable.

To create a new Message Variable, select **Create Message Variable** from the Message Variable menu. The [Create Message Variable Dialog](#) appears:

1. Provide a name for the variable.
2. Click **OK**.

Note that Message Type Namespace and Message Type are displayed automatically in the Properties view once the variable is defined.

If you select **Fault**, you must specify either a **WSDL Fault** or propagate a **SOAP Fault**.

**Note:** In some circumstances, no Faults or only a SOAP Fault will be available. See previous notes.

If you select a WSDL Fault, you must specify the Fault by name and define the Message Variable that it will be assigned to.

1. Select **WSDL Fault Name** and choose a name from those available.

**Note:** There may only be one name available in which case no choice is necessary.

2. Define a Message Variable. This can be done in two ways:
  - a. Select a pre-existing variable from the Message Variable menu.
  - b. Create a new Message Variable (following steps).

**Note:** If there are no available Message Variables associated with the previously chosen operation, you *must* create a new Message Variable.

To create a new Message Variable, select “Create Message Variable” from the Message Variable menu. The [Create Message Variable Dialog](#) opens:

1. Provide a name for the variable.
2. Click **OK**.

Note that Message Type Namespace and Message Type are displayed automatically on the properties page once a variable is defined.

If you select Propagate SOAP Fault, the SOAP Fault specified in the parent Error Handler will automatically be propagated in the Reply. There is nothing else to be configured

## Adding General Information

General information is useful for making a node more legible. It includes the ability to add a unique identifier, or Label, to the node and to supplement it with notes, or Documentation. General information is optional.

1. To add a Label to a node, open the Properties view and enter a unique, identifying string in the **Label** field. The Label that you enter appears underneath the node in the Canvas area. Alternatively, you can simply double-click the string under the icon and edit.
2. To add Documentation to a node, open the Properties view and enter any notes that you think are important in the **Documentation** field.

## About Scope

A Scope is a container that groups various elements together. The container creates a context that influences the behavior of its enclosed elements. Local Variables and the Error Handler defined

within the Scope are restricted to this context. However, some nodes within the scope may operate both locally (that is, within the Scope) and globally (that is, outside of the Scope.) For instance, an Invoke External Service within a certain Scope might call upon a service external to the Scope's context.

### Related Topics

- [Split-Join Properties View – Scope](#)

## Exporting and Testing a Split-Join

You can export and test a Split-Join on an ALSB server provided that it is associated with a transport typed business service. Exporting and testing a Split-Join can include the following tasks:

- Creating a Transport Typed Business Service
- Exporting the Split-Join Files
- Testing the Split-Join in the Test Console

## Creating a Transport Typed Business Service

A Split-Join is used by a particular transport typed business service. If you do not have an appropriate business service, you must create one before you can export or test your Split-Join. There are two ways to create a business service:

1. Create the business service manually in WorkSpace Studio or the ALSB console.
2. Generate the business service automatically from the Split-Join (.flow) menu:
  - a. Right click on the Split-Join (.flow) file in the Project Explorer to open the Split-Join menu.
  - b. Select **AquaLogic Service Bus**.
  - c. Select **Generate Business Service**.
  - d. Name and save the new service in a project.

After you create the business service, you can export the Split-Join provided that it has no errors.

**Note:** It is a helpful practice to place the associated business service in the same ALSB project as the Split-Join. It can also be useful to give the business service the same name as the Split-Join so that they are easily correlated.

## Exporting the Split-Join Files

Split-Joins without errors can be exported to an ALSB server.

**Note:** Errors appear in the Problems view of the Split-Join editor. If you try to export a Split-Join with errors, the export fails.

There are three ways to export a Split-Join:

1. Export from the Business Service Menu
2. Auto-export
3. Manual export

### Exporting from the Business Service Menu

It is possible to export a Split-Join directly from the Business Service menu. However, because exporting by this method automatically launches the ALSB Test Console, it is useful if you want to both export and test. Exporting from the Business Service menu involves the following steps:

1. In the Project Explorer, right click on the Business Service (.biz file) to be exported/tested.
2. Select **Run as**.
3. Select **Run on server**. The Run on Server Dialog opens.
4. Select an existing server or define a new one and go to the next step.
5. In the Add and Remove Projects window, the ALSB project containing the business service and any other dependent files have been pre-selected for configuration/export. They can not be removed because the business service can not be tested without its dependent files. The entire Split-Join will therefore be exported.
6. Select **Finish**, and the ALSB Test Console will launch. You can now test the business service.

### Auto-export

A Split-Join can be auto-exported to an ALSB server. If you use this method, you must manually launch the ALSB console in order to test the exported files. Auto-exporting involves the following steps:

1. Select **File > Export**.
2. Select **AquaLogic Service Bus**.

3. Select **Resources to ALSB Server**. This will export the resources to the ALSB server, but it will not launch the ALSB Test Console. You must launch the Test Console manually within the ALSB console application.

## Manual export

A Split-Join can be manually exported to an ALSB server. If you use this method, you must manually launch the ALSB console to test the exported files. Manually exporting involves the following steps:

1. Select **File > Export**.
2. Select **AquaLogic Service Bus**.
3. Select **Resources as Configuration JAR** and go to the next step.
4. In the ALSB Configuration JAR Export window, configure the following options:
  - a. Select the ALSB Configuration file containing the files to be exported.
  - b. Set the Export Level to **Project** or **Resource** depending upon whether you wish to export entire projects or individual files. The selection available in the tree below will change based upon the Export Level.
  - c. Select the projects and/or resources to be exported in the configuration JAR.
  - d. Select **Include Dependencies** if you want to export any file dependencies associated with the selected files.
  - e. Browse to a destination for the exported JAR file.
  - f. Click **Finish** to export the JAR file.
5. Import the JAR file via the ALSB console.

**Note:** A quick way to access the ALSB console from the IDE is to select **Launch ALSB Administration Console** from the server menu. (Right-click the appropriate server in the Servers view.)

## Testing the Split-Join in the Test Console

You can test a Split-Join by executing the business service that uses it in the ALSB Test Console. This can either be done within the Split-Join editor or by exporting the Split-Join to an ALSB server. To test the Split-Join within the IDE, you need to export the files using the menu for the business service that uses the Split-Join.

## Exporting from the Business Service Menu

You can export and test a Split-Join directly from the Business Service menu. If you use this method, the export happens in the background while the ALSB Test Console launches. Exporting from the Business Service menu involves the following steps:

1. In the Project Explorer, right click on the Business Service (.biz file) to be exported/tested.
2. Select **Run as**.
3. Select **Run on server**. The Run on Server Dialog appears.
4. Select an existing server or define a new one and go to the next step.
5. In the Add and Remove Projects window, the ALSB project containing the business service and any other dependent files have been pre-selected for configuration/export. The dependent files cannot be removed because the business service cannot be tested without its dependent files.

Click **Finish**, and the ALSB Test Console will launch. You can now test the business service.

**Note:** Although only the ALSB Test Console is displayed at this point, the entire Split-Join has been exported to the ALSB server.

# User Interface Reference

This section describes all the views, dialogs, wizards, and other user interface objects in the ALSB plug-in.

## Alerts

The following pages are provided for managing alerts:

- [Alert Destination editor](#)
- [Edit E-mail Recipient page](#)
- [Edit JMS Destination page](#)

### Alert Destination editor

An alert destination is a destination address for alert notifications in ALSB. Use this page to configure an alert destination resource. For more information, see [Alert Destinations](#) in *Using the AquaLogic Service Bus Console*.

Option	Description
Description	Enter a description for this alert destination.

Option	Description
SNMP Trap	If you specify <b>SNMP Trap</b> , alerts are sent as SNMP traps, and can be processed by any third-party enterprise monitoring systems (ESM).
Reporting	If you specify <b>Reporting</b> , alerts are sent to the ALSB Reporting module and can be captured using a custom reporting provider that can developed using the reporting APIs provider by AquaLogic Service Bus. This allows third-parties to receive and process alerts in custom Java code.

Continue in the Edit Alert Destination page. Click **Add** to add e-mail and JMS recipients to an alert destination. See:

- [“Edit E-mail Recipient page” on page 3-2](#)
- [“Edit JMS Destination page” on page 3-4](#)

For more information, see [Adding E-Mail and JMS Recipients](#) in *Using the AquaLogic Service Bus Console*.

## Edit E-mail Recipient page

Use this page to configure the destination target for an alert sent via e-mail (that is, using the e-mail transport). For more information, see [Adding E-Mail Recipients](#) in *Using the AquaLogic Service Bus Console*.

Option	Description
Mail Recipients	<p>Enter an e-mail recipient in the format:  <code>mailto:username@hostname</code></p> <p>You can specify multiple e-mail recipients by entering the user names and hostnames in a comma-separated list. For example,  <code>mailto:username@hostname</code>  <code>[ ,username_1@hostname_1 ] . . . [ ,username_n@hostname_n ]</code></p> <p>Only the first mail recipient needs to be prefixed with the text “mailto:”. However doing so is optional; the code will add it if it is missing.</p>
SMTP Server	<p>Select the name of the SMTP server for the outgoing e-mail. This field is not required if <b>Mail Session</b> is selected in the next field. These fields are mutually exclusive; it is an error to configure both.</p>
Mail Session	<p>Select an available mail session. This field is not required if an <b>SMTP Server</b> is selected in the previous field. These fields are mutually exclusive; it is an error to configure both.</p>
From Name	<p>Provide a sender’s name for the alert notification. This field is optional.</p>
From Address	<p>Provide a valid e-mail address. This field is required if a value for the <b>From Name</b> field is specified.</p>
Reply To Name	<p>Provide a name to which a reply may be addressed. This field is optional.</p>
Reply To Address	<p>Provide an e-mail address to which a reply may be sent. This field is required if a value for the <b>Reply To Name</b> field is specified.</p>
Connection Timeout	<p>Enter the number of seconds a connection must wait for a response from the server before timing out. The default value is 0.</p>
Request Encoding	<p>Enter a character set encoding value. The default encoding value is <code>iso-8859-1</code>.</p>

## Edit JMS Destination page

Use this page to configure the destination target for an alert sent via JMS (that is, using the JMS transport). For more information, see [Adding JMS Recipients](#) in *Using the AquaLogic Service Bus Console*.

Option	Description
Destination URI	Enter a JMS destination URI in the format: <code>jms://host:port/factoryJndiName/destJndiName</code>
Destination Type	Select <b>Queue</b> or <b>Topic</b> .
Message Type	Select <b>Bytes</b> or <b>Text</b> .
Request Encoding	Enter a character set encoding value. The default encoding value is <code>iso-8859-1</code> .

## AquaLogic Business Service Configuration

You configure new business services while creating them in the New AquaLogic Business Service wizard. You can view and modify those settings in the AquaLogic Business Service editor: With a few exceptions, configuration options are identical in the wizard and the editor and are therefore documented in one place. The wizard and editor business service configuration pages are:

- [“Business Service General Configuration page”](#) on page 3-4
- [“Business Service Message Type Configuration page”](#) on page 3-7
- [“Business Service Service Policy Configuration page”](#) on page 3-9
- [“Business Service SOAP Binding Configuration page”](#) on page 3-9
- [“Business Service Transport Configuration page”](#) on page 3-9

### Business Service General Configuration page

Use the AquaLogic Business Service General Configuration page to specify general configuration settings for a business service. This page appears both in the New AquaLogic

Business Service wizard and in the AquaLogic Business Service editor. Options vary, depending on whether you are using the wizard or the editor, as described below.

## New AquaLogic Business Service Wizard Options

The following table describes the options in the wizard:

Option	Description
Description	Enter a description for this service.
<b>Service Type - Create a New Service (wizard only)</b>	
A service type defines the types and packaging of the messages exchanged by the service. Select the type of business service to create:	
WSDL Web Service	Select this option to create a business service based on a WSDL. Then, enter the WSDL name, qualified by its path (for example, <code>myProject/myFolder/myWSDL</code> ). Alternatively, click <b>Browse</b> to select a WSDL resource.  ( <b>port or binding</b> ) - Enter the name of a port (defined in the WSDL) to describe an actual transport address, or enter the name of a binding (defined in the WSDL) to map to a transport address. If you use <b>Browse</b> to select a WSDL, as described above, the <b>Select a WSDL Definition</b> dialog lists any ports and bindings defined in the WSDL. When you choose a port or a binding on that page, the ( <b>port or binding</b> ) field is filled with the selected name.
Transport Typed Service	Select this option to create a service that uses EJB transport.
Messaging Service	Select this option to create a service that exchanges messages of different content-types. These exchanges can be either request/response or one-way. They can also have a response with no request when used with the HTTP 'GET' option for the HTTP transport. Unlike Web Services, the content-type of the request and response need not be the same.
Any SOAP Service	Select this option to create a SOAP service that does not have an explicitly defined, concrete interface.  Select <b>SOAP 1.1</b> or <b>SOAP 1.2</b> from the drop-down list to specify the SOAP version to be used.

Option	Description
Any XML Service	<p>Select this option to create an XML service that does not have an explicitly defined, concrete interface.</p> <p>HTTP GET is only supported for messaging services and this service type.</p>
<b>Service Type - Create From Existing Service</b>	
Choose one of these options to create a service based on another service.	
Business Service	<p>Select this option to clone an existing business service.</p> <p>Enter the path (<code>project/folder</code>) and the name of the business service; or click <b>Browse</b> to select a service.</p> <p>Since ALSB does not accept the same URI for multiple services, you must change the URI for the cloned service.</p>
Proxy Service	<p>Select this option to create a business service based on an existing proxy service.</p> <p>Enter the path (<code>project/folder</code>) and the name of the proxy service; or click <b>Browse</b> to select a service.</p> <p>Since ALSB does not accept the same URI for multiple services, you must change the URI for the cloned service.</p>

## AquaLogic Business Service Editor Options

The following table describes the options in the editor:

Option	Description
Description	Enter or modify a description for this service.
Service Type (editor only)	<p>This option shows the service type of the business service. You can change only some of the properties of some of the service types:</p> <ul style="list-style-type: none"> <li>• <b>WSDL Web Service</b> - You can enter (or click <b>Browse</b> to select) a different port or binding from the same WSDL. You can also specify a different WSDL, but by doing so, you are effectively creating a new service and you will have to configure it as if it were a new service.</li> <li>• <b>Transport Typed Service</b> - This option cannot be modified.</li> <li>• <b>Messaging Service</b> - This option cannot be modified.</li> <li>• <b>Any SOAP Service</b> - You can change the SOAP version (SOAP 1.1 or SOAP 1.2)</li> <li>• <b>Any XML Service</b> - This option cannot be modified.</li> </ul>

## Business Service Message Type Configuration page

Use the AquaLogic Business Service Message Type Configuration page to configure message types for a business service whose type is Messaging Service. This page appears both in the New AquaLogic Business Service wizard and in the AquaLogic Business Service editor:

The binding definition for messaging services consists of configuring the content-types of the messages that are exchanged. The content-type for the response does not need to be the same as for the request; therefore, the response is configured separately (for example, the service could accept an MFL message and return an XML acknowledgment receipt).

**Note:** E-mail, File, FTP, or SFTP transport business services whose type is Messaging Service support one-way messaging *only*; the **Response Message Type** should be **None**. If you select an option other than **None**, the file, ftp, or sftp protocol will not be available on the Transport Configuration page.

Option	Description
Request Message Type	<p>Select a message type for the request message:</p> <ul style="list-style-type: none"> <li>• <b>None</b> - Select this option if there is no request message (HTTP GET example)</li> <li>• <b>Binary</b> - Select this option if the content-type of the message is unknown or not important.</li> <li>• <b>Text</b> - Select this option if the message can be restricted to text.</li> <li>• <b>MFL</b> - Select this option if the message is a binary document conforming to an MFL definition. Enter the MFL file name (qualified by its path), or click <b>Browse</b> to select a file. You can configure only one MFL file. <b>Note:</b> To support multiple MFL files, define the content as binary or text and use the MFL action in the message flow to convert to XML.</li> <li>• <b>XML</b> - Select this option if the message is an XML document. Enter the XML file name (qualified by its path), or click <b>Browse</b> to select a file. Optionally provide some type information by declaring (in the <b>element or type</b> field) the XML schema type of the XML document exchanged.</li> </ul>
Response Message Type	<p>Select a message type for the response message:</p> <ul style="list-style-type: none"> <li>• <b>None</b> - Select this option if there is no response message.</li> <li>• <b>Binary</b> - Select this option if the content-type of the message is unknown or not important.</li> <li>• <b>Text</b> - Select this option if the message can be restricted to text.</li> <li>• <b>MFL</b> - Select this option if the message is a binary document conforming to an MFL definition. Enter the MFL file name (qualified by its path), or click <b>Browse</b> to select a file. You can configure only one MFL file. <b>Note:</b> To support multiple MFL files, define the content as binary or text and use the MFL action in the message flow to convert to XML.</li> <li>• <b>XML</b> - Select this option if the message is an XML document. Enter the XML file name (qualified by its path), or click <b>Browse</b> to select a file. Optionally provide some type information by declaring (in the <b>element or type</b> field) the XML schema type of the XML document exchanged.</li> </ul>

## Business Service Service Policy Configuration page

Use the AquaLogic Business Service Service Policy Configuration page to configure service policy settings for a proxy service. This page appears both in the New AquaLogic Business Service wizard and in the AquaLogic Business Service editor.

Option	Description
WSDL-Based Policy	Select this option if the service policy is associated with the WSDL upon which the service is based.
Custom Policy Bindings	Select this option to add service-level policies, operation-level policies (in which case the policy applies to both the request and response messages), request policies, and response policies directly.  For more information about configuring service policies, see <a href="#">Configuring Message Level Security for Web Services</a> in the <i>AquaLogic Service Bus Security Guide</i> .

## Business Service SOAP Binding Configuration page

Use AquaLogic Business Service SOAP Binding Configuration page to configure the SOAP Binding for a business service based on a WSDL. This page appears both in the New AquaLogic Business Service wizard and in the AquaLogic Business Service editor:

Select or deselect **Enforce WS-I Compliance** to specify whether or not the service is to conform to the Basic Profile defined by the Web Services Interoperability Organization. This option is available for or SOAP 1.1 services only

When a service is marked WS-I compliant, checks are performed against the messages sent to and from that service.

## Business Service Transport Configuration page

Use the AquaLogic Business Service Transport Configuration page to select, review, or change the service's transport protocol and to set, review, or change general transport configuration settings. This page appears both in the New AquaLogic Business Service wizard and in the AquaLogic Business Service editor:

Outbound transport-level security applies to the connections between ALSB proxy services and business services. For more information about transport-level security, see [Configuring Transport-Level Security](#) in the *AquaLogic Service Bus Security Guide*.

Option	Description
Protocol	<p>Select a transport protocol from the list. The protocols available differ, depending on the service type:</p> <ul style="list-style-type: none"> <li>• <b>WSDL Web Service:</b> DSP, HTTP, JMS, JPD, SB, WS</li> <li>• <b>Transport-Typed Service:</b> EJB, Flow</li> <li>• <b>Messaging Service:</b> E-mail, File, FTP, HTTP, JMS, MQ (if available), SFTP, Tuxedo</li> <li>• <b>Any SOAP Service:</b> DSP, HTTP, JMS, JPD, SB</li> <li>• <b>Any XML Service:</b> DSP, E-mail, File, FTP, HTTP, JMS, JPD, MQ (if available), SB, SFTP, Tuxedo</li> </ul>
Load Balancing Algorithm	<p>Select one of these load-balancing algorithms:</p> <ul style="list-style-type: none"> <li>• <b>Round-robin</b> - This algorithm dynamically orders the URLs that you enter in the <b>Endpoint URI</b> field for this business service. If the first one fails, it tries the next one, and so on until the retry count is exhausted. For every new message, there is a new order of URLs.</li> <li>• <b>Random</b> - This algorithm randomly orders the list of URLs that you enter in the <b>Endpoint URI</b> field for this business service. If the first one fails, it tries the next one, and so on until the retry count is exhausted.</li> <li>• <b>Random-weighted</b> - This algorithm randomly orders the list of URLs that you enter in the <b>Endpoint URI</b> field for this business service, but some are retried more than others based on the value you enter in the <b>Weight</b> field.</li> <li>• <b>None</b> - This algorithm orders the list of URLs that you enter in the <b>Endpoint URI</b> field for this business service from top to bottom.</li> </ul>

Option	Description
Endpoint URI	<p data-bbox="354 357 1197 409">Enter an endpoint URL in the format based on the transport protocol you selected in the <b>Protocol</b> field, above: The formats are:</p> <ul data-bbox="354 423 1251 1532" style="list-style-type: none"> <li data-bbox="354 423 975 449">• <b>DSP</b> - <code>t3://dsp-ip-address:port/dsp-app-name</code></li> <li data-bbox="354 463 747 489">• <b>EJB</b> - <code>ejb:provider:jndiname</code>  <p data-bbox="391 499 1251 552">In the URI, <code>provider</code> is the name of the JNDI provider resource, and <code>JNDIname</code> is the JNDI name in the JNDI server for the EJB.</p> <p data-bbox="391 565 1251 618">If the JNDI provider is located on the same server, the JNDI provider need not be specified. The URI then would be <code>ejb::jndiname</code></p> </li> <li data-bbox="354 631 733 657">• <b>E-mail</b> - <code>mailto:foo@bar.com</code></li> <li data-bbox="354 671 740 697">• <b>File</b> - <code>file:///root-dir/dir1</code></li> <li data-bbox="354 711 857 737">• <b>FTP</b> - <code>ftp://hostname:port/directory</code></li> <li data-bbox="354 751 864 777">• <b>HTTP</b> - <code>http://host:port/someService</code>  <p data-bbox="391 788 1005 814">The HTTP transport supports both HTTP and HTTPS endpoints.</p> </li> <li data-bbox="354 828 1251 914">• <b>JMS</b> - <code>jms://host:port[,host:port]*/factoryJndiName/destJndiName</code>  <p data-bbox="391 861 1143 887">To target a JMS destination to multiple servers, use the following URI format:</p> <p data-bbox="391 890 1206 916"><code>jms://host1:port,host2:port/QueueConnectionFactory/DestName</code></p> </li> <li data-bbox="354 928 1251 1112">• <b>JPD</b> - <code>jpd:[&lt;provider&gt;]:&lt;jpd_uri&gt;</code>  <p data-bbox="391 961 1224 1013"><code>provider</code> (optional) is the name of the JNDI provider which corresponds to the WLI JNDI provider resource. When omitted, the JNDI provider on the local server is used.</p> <p data-bbox="391 1027 1251 1112"><code>&lt;jpd uri&gt;</code> is the relative URL of the JPD on the WLI server. For example, if <code>processes.Process.jpd</code> is in the <code>SampleApp Web</code> project, then the relative URL of the JPD is <code>/SampleApp/processes/Process.jpd</code>.</p> </li> <li data-bbox="354 1126 1251 1355">• <b>MQ</b> - <code>mq://local-queue-name?conn=mq-connection-resource-ref</code>  <p data-bbox="391 1159 1251 1220"><code>local-queue-name</code> is the name of the MQ queue from which the business service reads messages.</p> <p data-bbox="391 1230 1233 1291"><code>mq-connection-resource-ref</code> is the path (<code>project/folder</code>) and name of the MQ connection resource; for example, <code>default/my_MQconnection</code>.</p> <p data-bbox="391 1302 1201 1355">To make the MQ transport available in ALSB, see <a href="#">MQ Connections</a> in <i>Using the AquaLogic Service Bus Console</i>.</p> </li> <li data-bbox="354 1369 1224 1465">• <b>SB</b> - <code>sb://&lt;jndi_provider_name/&gt;service_name</code>  <p data-bbox="391 1407 1224 1459"><code>jndi_provider_name</code> (optional) is the name of the ALSB JNDI provider resource. When omitted, the default context is used.</p> <p data-bbox="391 1470 1217 1496"><code>service_name</code> is a target service and corresponds to the remote proxy service URI.</p> </li> <li data-bbox="354 1510 884 1536">• <b>SFTP</b> - <code>sftp://hostname:port/directory</code></li> </ul>

Option	Description
Endpoint URI (continued)	<ul style="list-style-type: none"> <li>• <b>Tuxedo</b> - <code>tuxedo:resourcename/remotename</code>  <code>tuxedo-queue:sendQSpace/sendQName[[rcvQspace:]rvcQname][failureQname]</code>  <p>In the URI, <code>resourcename</code> corresponds to a WTC Import name and <code>remotename</code> corresponds to the service name exported by the remote Tuxedo domain. The URI <code>resourcename</code> is required, and the <code>remotename</code> is optional.</p> <p>If more than one URI is specified, you must have unique resource names for the endpoints. If no remote name is specified, its value is the value of the resource name. If no remote name is entered or if remote and resource name are the same, only one URI is allowed. In this case resource name and remote name have the same value. This allows already defined WTC Imports to make use of WTC load-balancing and failover. For more information, see <a href="#">AquaLogic Service Bus Interoperability Solution for Tuxedo</a>.</p> </li> <li>• <b>WS</b> - <code>http://host:port/someService</code></li> </ul> <p><b>Note:</b> ALSB no longer supports duplicate endpoint URIs within the same business service. Click <b>Add</b> to add one or more additional URIs. At run time, the URLs are selected based on the load balancing algorithm you selected in the <b>Load Balancing Algorithm</b> field.</p> <p>If you selected <b>Random-weighted</b> in the <b>Load Balancing Algorithm</b> field, you can also enter a weight in the <b>Endpoint URI</b> field. The default is 1.</p> <p>If you have multiple endpoint defined, and you selected <b>None</b> in the <b>Load Balancing Algorithm</b> field, the order of endpoints is significant. You can reorder the endpoints using the <b>Up</b> and <b>Down</b> buttons.</p> <p>ALSB does not support duplicate endpoint URIs within the same business service.</p>
Retry count	<p>In case of delivery failure when sending outbound requests, specify the number of times to retry individual URL endpoints; in other words, the number of failover attempts.</p> <p>For example, a business service has one configured URI (U1) and the number of retries is set to 3. If U1 fails on the first attempt, the system retries the U1 endpoint 3 more times.</p> <p>If a business service has 2 configured URIs (U1 and U2) and a retry count of 3, if the first attempt (for example, to U1) fails, the system tries (fails over to) the next URI (U2). If that also fails, the system makes two more attempts, once to U1 and once to U2.</p>

Option	Description
Retry Iteration Interval	<p>Specify the number of seconds the system pauses before iterating over all the endpoint URIs in the list again.</p> <p>For example, a business service has two configured URIs (U1 and U2) and a retry count of 2 with a retry iteration interval of 5 seconds. If the first attempt (to U1) fails, the system tries U2 right away. But if U2 also fails, the system waits for 5 seconds and retries U1 once more.</p>
Retry Application Errors	<p>Select <b>Yes</b> or <b>No</b>.</p> <p>In case of delivery failure when sending outbound requests, specify whether or not to retry endpoint URIs based on application errors (for example, a SOAP fault).</p>

## AquaLogic Proxy Service Configuration

You configure new proxy services while creating them in the New AquaLogic Proxy Service wizard. You can view and modify those settings in the AquaLogic Proxy Service editor: With a few exceptions, configuration options are identical in the wizard and the editor and are therefore documented in one place. The wizard and editor business service configuration pages are:

- [“Proxy Service General Configuration page” on page 3-13](#)
- [“Proxy Service Message Level Security Configuration page” on page 3-16](#)
- [“Proxy Service Message Type Configuration page” on page 3-19](#)
- [“Proxy Service Operation Selection Configuration page” on page 3-22](#)
- [“Proxy Service Service Policy Configuration page” on page 3-25](#)
- [“Proxy Service SOAP Binding Configuration page” on page 3-26](#)
- [“Proxy Service Transport Configuration page” on page 3-27](#)

### Proxy Service General Configuration page

Use the AquaLogic Proxy Service General Configuration page to set or modify general configuration properties for a proxy service. This page appears both in the New AquaLogic Proxy Service wizard and in the AquaLogic Proxy Service editor: Options vary, depending on whether you are using the wizard or the editor, as described below.

## New AquaLogic Proxy Service Wizard Options

The following table describes the options in the wizard:

Option	Description
Description	Enter a description for this proxy service.
Service Type - Create a New Service	Select the type of proxy service to create, as described below.
WSDL Web Service	<p>Select this option to create a proxy service based on a WSDL. Then enter the WSDL name, qualified by its path (for example, <code>myProject/myFolder/myWSDL</code>). Alternatively, click <b>Browse</b> to select a WSDL resource.</p> <p><b>(port or binding)</b> - Enter the name of a port (defined in the WSDL) to describe an actual transport address, or enter the name of a binding (defined in the WSDL) to map to a transport address. If you use <b>Browse</b> to select a WSDL, the <b>Select a WSDL Definition</b> dialog lists any defined ports and bindings.</p> <p><b>Note:</b> If you are going to use the SOAP Body Type for operations, ensure that the WSDL does not have two operations with the same input message. The SOAP Body Type operation cannot be uniquely identified by inspecting the input message.</p>
Messaging Service	<p>Select this option to create a service that can receive messages of one data type and respond with messages of a different data type. These exchanges can be either request/response or one-way.</p> <p>(HTTP GET is supported only in the Any XML Service and Messaging Service service types.)</p>
Any SOAP Service	<p>Select this option to create a SOAP service that does not have an explicitly defined, concrete interface.</p> <p>Select <b>SOAP 1.1</b> or <b>SOAP 1.2</b> from the drop-down list to specify the SOAP version to be used.</p>
Any XML Service	<p>Select this option to create an XML service that does not have an explicitly defined, concrete interface.</p> <p>(HTTP GET is supported only in the Any XML Service and Messaging Service service types.)</p>

Option	Description
Service Type - Create From Existing Service	<p>Choose one of these options to create a service based on another service.</p> <p><b>Note:</b> When a proxy service is created from another service, alert rules are maintained in the following way:</p> <ul style="list-style-type: none"> <li>– When a proxy service is created from a business service or a business service is created from a proxy service, the alert rules, if any, are removed.</li> <li>– When a proxy service is created from another proxy service or a business service is created from another business service, the alert rules, if any, are retained.</li> </ul>
Business Service	<p>Select this option to create a proxy service with a route node that routes to the business service you select. You cannot create a proxy service from a transport typed business service. If you create a proxy service from a DSP transport business service, ALSB switches the transport type of the proxy service to HTTP, because the DSP transport cannot be used for proxy services. You can change the transport type of the proxy service to any other available transport.</p> <p>Enter the path (<code>project/folder</code>) and the name of the business service; or click <b>Browse</b> to select a service.</p>
Proxy Service	<p>Select this option to clone an existing proxy service. Enter the path (<code>project/folder</code>) and the name of the proxy service, or click <b>Browse</b> to select a service.</p> <p>Since ALSB does not accept the same URI for multiple services, you must change the URI for the cloned service.</p>
Content Streaming	<p>Select this option to stream message content rather than store it in memory.</p> <p>Select the <b>Enabled</b> check box and whether to buffer the intermediate content in memory (<b>Memory Buffer</b>) or to a disk file (<b>Disk Buffer</b>).</p> <p>For more information, see <a href="#">Streaming body Content</a> in the <i>AquaLogic Service Bus User Guide</i>.</p>

## AquaLogic Proxy Service Editor Options

The following table describes the options in the editor:

Option	Description
Description	Enter a description for this proxy service.
Service Type (editor only)	<p>This option shows the service type of the proxy service. You can change only some of the properties of some of the service types:</p> <ul style="list-style-type: none"> <li>• <b>WSDL Web Service</b> - You can enter (or click <b>Browse</b> to select) a different port or binding from the same WSDL. You can also specify a different WSDL, but by doing so, you are effectively creating a new service and you will have to configure it as if it were a new service.</li> <li>• <b>Transport Typed Service</b> - This option cannot be modified.</li> <li>• <b>Messaging Service</b> - This option cannot be modified.</li> <li>• <b>Any SOAP Service</b> - You can change the SOAP version (SOAP 1.1 or SOAP 1.2)</li> <li>• <b>Any XML Service</b> - This option cannot be modified.</li> </ul>
Content Streaming	<p>Select this option to stream message content rather than store it in memory.</p> <p>Select the <b>Enabled</b> check box and whether to buffer the intermediate content in memory (<b>Memory Buffer</b>) or to a disk file (<b>Disk Buffer</b>).</p> <p>For more information, see <a href="#">Streaming body Content</a> in the <i>AquaLogic Service Bus User Guide</i>.</p>

## Proxy Service Message Level Security Configuration page

Use the AquaLogic Proxy Service Message Level Security Configuration page to configure message-level security for the proxy service. This page appears both in the New AquaLogic Proxy Service wizard and in the AquaLogic Proxy Service editor:

Message-level custom tokens and message-level user name and password are supported on proxy services of the following binding types:

- WSDL-SOAP
- WSDL-XML
- Abstract SOAP
- Abstract XML
- Mixed - XML (in the request)

- Mixed - MFL (in the request)

The configuration for both custom user name/password and custom token is similar. In both cases, you specify XPath expressions that enable ALSB to locate the necessary information. The root of these XPath expressions is as follows:

- Use `soap-env:Envelope/soap-env:Header` if the service binding is AnySOAP or WSDL-SOAP.
- Use `soap-env:Body` if the service binding is not SOAP based.

All XPath expressions must be in a valid XPath 2.0 format. The XPath expressions must use the XPath "declare namespace" syntax to declare any namespaces used, as follows:

```
declare namespace
ns='http://webservices.mycompany.com/MyExampleService';)
```

Option	Description
Service Key Provider	<p>The name of a service key provider to be used by the service.</p> <p>You can enter the path (<code>project/folder</code>) and name of a service key provider, or click <b>Browse</b> to select one.</p> <p>A service key provider is only required in certain cases:</p> <ul style="list-style-type: none"> <li>• Outbound two-way TLS/SSL, where the proxy service routes messages to HTTPS services that require client-certificate authentication.</li> <li>• In some Web Service security scenarios, for example, if the proxy service requires messages to be encrypted.</li> </ul> <p>To add a Web service security-enabled proxy service, you must create the proxy service from a WSDL (port or binding) with WS-policy attachments.</p>
Custom Authentication Settings	<p>Select one of the following:</p> <ul style="list-style-type: none"> <li>• <b>None</b> - if the service will not use custom authentication.</li> <li>• <b>Custom User Name and Password</b> - if the service will use a custom name and password, specified as XPath expressions</li> <li>• <b>Custom Token</b> - if the service will use a custom token</li> </ul>

Option	Description
Custom User Name and Password - User Name XPath	The user name, specified as an XPath expression. The XPath expression is evaluated against the message headers or payload, as appropriate, which allows ALSB to obtain the user name and for custom authentication.
Custom User Name and Password - User Password XPath	The password, specified as an XPath expression. The XPath expression is evaluated against the message headers or payload, as appropriate, which allows ALSB to obtain the password values for custom authentication.
Custom Token - Token Type	Enter the type for the custom token type. Only the active token types configured for a WebLogic Server Identity Assertion provider can be used.  See <a href="#">Configuring Identity Assertion Providers for Custom Tokens</a> for more information.

Option	Description
Custom Token - Token XPath	<p>An XPath expression that specifies a path to the custom token. ALSB evaluates the Token XPath expression against the message headers or payload, as appropriate, to obtain the token for custom authentication.</p> <p>To create or edit an expression, click &lt;XPath&gt; (or the <i>expression_fragment</i>, if one is already defined) to display the <a href="#">XPath Expression Editor</a>.</p>
Custom User Name and Password - Context Properties <i>or</i> Custom Token - Context Properties	<p>Optionally, specify one or more context properties to pass additional context information to the Authentication (Custom User Name and Password) or Identity Assertion (Custom Token) security provider.</p> <p>Context Properties provide a way (the <code>ContextHandler</code> interface) to pass additional information to the WebLogic Security Framework so that a security provider can obtain contextual information. See <a href="#">Additional Context Properties for Message Level Authentication</a> for more information.</p> <p>Enter the <b>Property Name</b> as a literal string, and the <b>Value Selector</b> as a valid XPath expression. (XPath expressions can also be literal strings.)</p> <p>The XPath expressions are evaluated against the same message-part that is used for the custom token or custom user name/password. That is, the <b>Value Selector</b> XPath expressions for SOAP-based proxy services evaluate against the header and against the payload for non-SOAP-based proxy services.</p> <p>The XPath expression is evaluated at runtime to produce the property's value. A <code>ContextHandler</code> is essentially a name/value list and, as such, it requires that a security provider know what names to look for. Therefore, the XPath expressions are evaluated only if a security provider asks for the value of one of these user-defined properties.</p> <p>Click <b>Add Property</b> to add this context property. You can add multiple context properties.</p>

## Proxy Service Message Type Configuration page

Use AquaLogic Proxy Service Message Type Configuration page to configure message types for a proxy service whose type is Messaging Service. This page appears both in the New AquaLogic Proxy Service wizard and in the AquaLogic Proxy Service editor:

The binding definition for messaging services consists of configuring the content-types of the messages that are exchanged. The content-type for the response does not have to be the same as

for the request; therefore, the response is configured separately (for example, the service could accept an MFL message and return an XML acknowledgment receipt).

**Note:** E-mail, File, FTP, or SFTP transport proxy services whose type is Messaging Service support one-way messaging *only*; the **Response Message Type** should be **None**. If you select an option other than **None**, the E-mail, File, FTP, or SFTP protocols will not be available on the Transport Configuration page.

Option	Description
Request Message Type	<p>Select a message type for the request message:</p> <ul style="list-style-type: none"> <li>• <b>None</b> - Select this option if there is no request message.</li> <li>• <b>Binary</b> - Select this option if the content-type of the message is unknown or not important.</li> <li>• <b>Text</b> - Select this option if the message can be restricted to text.</li> <li>• <b>MFL</b> - Select this option if the message is a binary document conforming to an MFL definition. Enter the MFL file name (qualified by its path), or click <b>Browse</b> to select a file. You can configure only one MFL file. <b>Note:</b> To support multiple MFL files, define the content as binary or text and use the MFL action in the message flow to convert to XML.</li> <li>• <b>XML</b> - Select this option if the message is an XML document. Enter the XML file name (qualified by its path), or click <b>Browse</b> to select a file. Optionally provide some type information by declaring (in the <b>element or type</b> field) the XML schema type of the XML document exchanged.</li> </ul>
Response Message Type	<p>Select a message type for the response message:</p> <ul style="list-style-type: none"> <li>• <b>None</b> - Select this option if there is no response message.</li> <li>• <b>Binary</b> - Select this option if the content-type of the message is unknown or not important.</li> <li>• <b>Text</b> - Select this option if the message can be restricted to text.</li> <li>• <b>MFL</b> - Select this option if the message is a binary document conforming to an MFL definition. Enter the MFL file name (qualified by its path), or click <b>Browse</b> to select a file. You can configure only one MFL file. <b>Note:</b> To support multiple MFL files, define the content as binary or text and use the MFL action in the message flow to convert to XML.</li> <li>• <b>XML</b> - Select this option if the message is an XML document. Enter the XML file name (qualified by its path), or click <b>Browse</b> to select a file. Optionally provide some type information by declaring (in the <b>element or type</b> field) the XML schema type of the XML document exchanged.</li> </ul>

## Proxy Service Operation Selection Configuration page

Use AquaLogic Proxy Service Operation Selection Configuration page to enforce WS-I compliance (for SOAP 1.1 services only) and select the selection algorithm to use to determine the operation called by this proxy service. This option is only available for SOAP or XML services defined from a WSDL.

The WSDL specification defines a default algorithm to compute which operation is called based on the type of the SOAP message received. However, there are cases (for example, performance issues, signature/encryption issues, or the default algorithm is not applicable) when you may need to select the operation based on other means.

ALSB provides additional algorithms. Each of them follows the same pattern and are based on the evaluation of an expression to get a value that is then used to lookup the corresponding operation in a static table.

ALSB is generally very forgiving if an inbound message is either missing data such that the operation cannot be determined, or has data that does not correspond to a valid operation. Both of these conditions result in `$operation` being empty. Rather than reject all such messages, ALSB does not initialize the operation variable in the context but otherwise continues to process the message.

However, security requirements are enforced if the proxy service is WSDL-based and at least one of the following conditions is true:

- The WSDL has a WS-Security policy and the proxy is an active intermediary.
- The proxy has message-level custom authentication (either custom token or username/password).

If these conditions are met, then there is a runtime check to make sure the operation selection algorithm returns a valid operation name. If the operation selection returns null or an operation that is not in the WSDL, then the message is rejected and an error is raised.

---

Option	Description
Enforce WS-I Compliance	<p data-bbox="525 401 1228 482">Select or deselect this check box to specify whether or not the service is to conform to the Basic Profile defined by the Web Services Interoperability Organization. This option is available for or SOAP 1.1 services only</p> <p data-bbox="525 499 1228 552">When a service is marked WS-I compliant, checks are performed against the messages sent to and from that service.</p> <p data-bbox="525 569 1228 826">For proxies, checks are performed against request messages received by the proxy. For invoked services (i.e. services invoked by a proxy via service callout action or route node), checks are performed against the response messages received from those services. Note that it is the WS-I compliance property of the invoked service and not the proxy that determines whether or not checks are performed against messages received from the invoked service. If you specify WS-I compliance testing for an invoked service, the message flow generates a fault for response errors.</p>

---

Option	Description
Selection Algorithm	<p>Select one of the following and perform any required additional steps:</p> <ul style="list-style-type: none"> <li>• <b>Transport Header</b> - Select this algorithm to define the transport header that contains the lookup value. Then: <ul style="list-style-type: none"> <li>– In the <b>Header Name</b> field, enter the transport header that extracts the value used as a key to select the operation being invoked.</li> <li>– Under the <b>Operation Mapping</b> field, specify the value for each operation in the <b>Value</b> field. The value is used as the key of the operation.</li> </ul> </li> <li>• <b>SOAPAction Header</b> - Select this algorithm to specify that operation mapping be done automatically from the WSDL associated with this proxy service.</li> <li>• <b>WS-Addressing</b> - Select this algorithm to specify that the lookup value is contained by the WS-Addressing <code>Action</code> tag located in the SOAP headers of the SOAP message. Then, under the <b>Operation Mapping</b> field, specify the value for each operation in the <b>Value</b> field. The value is used as the key of the operation.</li> <li>• <b>SOAP Header</b> - Select this algorithm to define an XPath expression to be evaluated against the SOAP headers. This allows you to get the lookup value. Then: <ul style="list-style-type: none"> <li>– In the <b>XPath Expression</b> field, specify the XPath expression that extracts the value used as a key to select the operation being invoked.</li> <li>– In the <b>Operation Mapping</b> field, specify the value for each operation in the <b>Value</b> field. The value is used as the key of the operation.</li> </ul> </li> <li>• <b>SOAP Body Type</b> - This is the default algorithm defined by the WSDL specification to compute which operation is called based on the type of the SOAP message received. <p>If the proxy service is configured for a Web Service security pass-through scenario with an encrypted body, you cannot select this algorithm. A similar caveat applies to pass-through encrypted SOAP headers.</p> <p>If you have a WSDL that has two operations with the same input message, do not select this algorithm for operations, because the operation cannot be uniquely identified by inspecting the input message.</p> </li> <li>• <b>Payload Type</b> - Available only for XML services based on a WSDL port or WSDL binding.</li> </ul>

Option	Description
Header Name	This option is available only when the <b>Selection Algorithm</b> option is set to <b>Transport Header</b> . Enter the transport header that extracts the value used as a key to select the operation being invoked.
XPath Expression	This option is available only when the <b>Selection Algorithm</b> option is set to <b>SOAPHeader</b> . Specify the XPath expression that extracts the value used as a key to select the operation being invoked.
Operation Mapping	This option is available only when the <b>Selection Algorithm</b> option is set to <b>Transport Header</b> , <b>WS-Addressing</b> , or <b>SOAP Body Type</b> . Specify the value for each operation in the <b>Value</b> field. The value is used as the key of the operation.

## Proxy Service Service Policy Configuration page

Use AquaLogic Proxy Service Service Policy Configuration page to configure service policies for a proxy service. This page appears both in the New AquaLogic Proxy Service wizard and in the AquaLogic Proxy Service editor:

Option	Description
WSDL-Based Policy	Select this option if the service policy is associated with the WSDL upon which the service is based.
Custom Policy Bindings	Select this option to add service-level policies, operation-level policies (in which case the policy applies to both the request and response messages), request policies, and response policies directly.  For more information about configuring service policies, see <a href="#">Configuring Message Level Security for Web Services</a> in the <i>AquaLogic Service Bus Security Guide</i> .

## Proxy Service SOAP Binding Configuration page

This page is displayed only if the service you are creating has operations. This page appears both in the New AquaLogic Proxy Service wizard and in the AquaLogic Proxy Service editor:

Use the AquaLogic Proxy Service SOAP Binding Configuration page to enforce WS-I compliance (for SOAP 1.1 services only) and select the selection algorithm to use to determine the operation called by this proxy service. This option is only available for SOAP or XML services defined from a WSDL.

The WSDL specification defines a default algorithm to compute which operation is called based on the type of the SOAP message received. However, there are cases (for example, performance issues, signature/encryption issues, or the default algorithm is not applicable) when you may need to select the operation based on other means.

ALSB provides additional algorithms. Each of them follows the same pattern and are based on the evaluation of an expression to get a value that is then used to lookup the corresponding operation in a static table.

ALSB is generally very forgiving if an inbound message is either missing data such that the operation cannot be determined, or has data that does not correspond to a valid operation. Both of these conditions result in `$operation` being empty. Rather than reject all such messages, ALSB does not initialize the operation variable in the context but otherwise continues to process the message.

However, security requirements are enforced if the proxy service is WSDL-based and at least one of the following conditions is true:

- The WSDL has a WS-Security policy and the proxy is an active intermediary.
- The proxy has message-level custom authentication (either custom token or user name/password).

If these conditions are met, then there is a runtime check to make sure the operation selection algorithm returns a valid operation name. If the operation selection returns null or an operation that is not in the WSDL, then the message is rejected and an error is raised.

Option	Description
Enforce WS-I Compliance	<p data-bbox="525 401 801 423">For SOAP 1.1 services only:</p> <p data-bbox="525 440 1228 522">Select or deselect this check box if you want to specify whether or not the service is to conform to the Basic Profile defined by the Web Services Interoperability Organization.</p> <p data-bbox="525 539 1228 826">When a service is marked WS-I compliant, checks are performed against the messages sent to and from that service. For proxies, checks are performed against request messages received by the proxy. For invoked services (i.e. services invoked by a proxy via service callout action or route node), checks are performed against the response messages received from those services. Note that it is the WS-I compliance property of the invoked service and not the proxy that determines whether or not checks are performed against messages received from the invoked service. If you specify WS-I compliance testing for an invoked service, the message flow generates a fault for response errors.</p>

## Proxy Service Transport Configuration page

Use the AquaLogic Proxy Service Transport Configuration page to select a transport protocol for the proxy service and to set other general transport configuration settings.

This page appears both in the New AquaLogic Proxy Service wizard and in the AquaLogic Proxy Service editor:

**Note:** Inbound transport-level security applies to the client applications and ALSB proxy services. Outbound transport-level security applies to the connections between ALSB proxy services and business services. To learn more about transport-level security, see [Configuring Transport-Level Security](#) in the *AquaLogic Service Bus Security Guide*.

---

Option	Description
Protocol	<p>Select a transport protocol from the list. The protocols available differ, depending on the service type you are creating:</p> <ul style="list-style-type: none"><li data-bbox="303 461 830 486">• <b>WSDL Web Service:</b> HTTP, JMS, Local, SB, WS</li><li data-bbox="303 499 1157 552">• <b>Messaging Service:</b> E-mail, File, FTP, HTTP, JMS, Local, MQ (if available), SFTP, Tuxedo</li><li data-bbox="303 565 771 590">• <b>Any SOAP Service:</b> HTTP, JMS, Local, SB</li><li data-bbox="303 604 1130 656">• <b>Any XML Service:</b> E-mail, File, FTP, HTTP, JMS, Local, MQ (if available), SB, SFTP, Tuxedo</li></ul>

---

Option	Description
Endpoint URI	<p>Enter an endpoint URI in the format based on the transport protocol you selected in the <b>Protocol</b> field, above: The formats are:</p> <ul style="list-style-type: none"> <li>• <b>E-mail</b> - mailfrom:mail-server-host:port</li> <li>• <b>File</b> - file:///root-dir/dir1</li> <li>• <b>FTP</b> - ftp://hostname:port/directory</li> <li>• <b>HTTP</b> - /someName</li> </ul> <p>The HTTP transport supports both HTTP and HTTPS endpoints.</p> <ul style="list-style-type: none"> <li>• <b>JMS</b> - jms://host:port[,host:port]*/factoryJndiName/destJndiName</li> </ul> <p>To target a target a JMS destination to multiple servers, use the following URI format: jms://host1:port,host2:port/QueueConnectionFactory/DestName</p> <p>Note that when you create a proxy service, you can configure a JMS endpoint URI even if the server at that endpoint is not available. However, in the case of JMS, when you activate the session, the endpoint must be available.</p> <ul style="list-style-type: none"> <li>• <b>Local</b> This transport does not require an endpoint URI.</li> <li>• <b>MQ</b> - mq://local-queue-name?conn=mq-connection-resource-ref local-queue-name is the name of the MQ queue from which the proxy service reads messages. mq-connection-resource-ref is the path (project/folder) and name of the MQ connection resource; for example, default/my_MQconnection. To make the MQ transport available in ALSB, see <a href="#">MQ Connections</a> in <i>Using the AquaLogic Service Bus Console</i>.</li> <li>• <b>SB</b> - service_name service_name is the unique identifier for the proxy service. By default, this name will be the proxy service name. service_name must only contain characters permitted in URIs (as described in <a href="#">RFC2396</a>), except it cannot contain forward slash (/) or colon (:) characters.</li> <li>• <b>SFTP</b> - sftp://hostname:port/directory</li> </ul>

Option	Description
Endpoint URI (continued)	<ul style="list-style-type: none"> <li>• <b>Tuxedo</b> - <code>servicename</code> The URI <code>servicename</code> corresponds to a WTC Export that the remote Tuxedo domain identifies as a Tuxedo service.  If more than one URI is specified, you must have unique resource names for the endpoints. If no remote name is specified, its value is the value of the resource name. If no remote name is entered or if remote and resource name are the same, only one URI is allowed. In this case resource name and remote name will have the same value. This allows users using already defined WTC Imports to make use of WTC load-balancing and failover.  <b>Note:</b> If you configure two identical URIs, an error indicates that the service name already exists.</li> <li>• <b>WS</b> - <code>/contextPath</code> <code>contextPath</code> must be unique for proxy services that use either HTTP or WS transport.</li> </ul>
Get All Headers	<p>Select <b>Yes</b> to retrieve all the headers from the transport.</p> <p>Select <b>No</b> to retrieve a defined set of headers. If you select <b>No</b>, enter a set of headers in the <b>Header</b> field, then click <b>Add</b>. (This step does not apply to Local transport.)</p> <p><b>Note:</b> ALSB does not pass the HTTP Authorization header from the request to the pipeline because it opens a security vulnerability. You could inadvertently create a log action that writes the user name and unencrypted password to a log file. If your design pattern requires the HTTP Authorization header to be in the pipeline, do the following:</p> <ol style="list-style-type: none"> <li>a. In the startup command for ALSB, set the following system property to true: <code>com.bea.wli.sb.transports.http.GetHttpAuthorizationHeaderAllowed</code></li> <li>b. In Eclipse, on the Transport Configuration page, select <b>Yes</b> for <b>Get All Headers</b> or select <b>No</b> and specify Authorization.</li> <li>c. Restart ALSB.</li> </ol> <p>ALSB will pass the Authorization header to the pipeline.</p>

## ALSB Configurations and Projects

The following are provided for working with ALSB configurations and projects.

- [ALSB Configurations view](#)
- [New AquaLogic Service Bus Configuration Project wizard](#)
- [New AquaLogic Service Bus Project wizard](#)

## ALSB Configurations view

This view displays a hierarchical list of all your ALSB configurations and the projects they contain. See also “[New AquaLogic Service Bus Configuration Project wizard](#)” on page 3-31.

You can do the following in the Configurations view:

- Edit the configuration :
  - a. Right click the configuration you want to edit.
  - b. Select **Properties** from the menu.
  - c. Modify information as needed in the [ALSB Configuration page](#).
- Create a new configuration:
  - a. Right-click anywhere in the view.
  - b. Select **New ALSB Configuration** from the menu.
  - c. Enter information as needed in the [ALSB Configuration page](#).
- Move a project from one configuration to another by dragging it from the source configuration to the target configuration. You can also drag a project from the Project Explorer.
- Delete a configuration project::
  - a. Right-click the configuration you want to delete.
  - b. Select **Delete** from the menu.

## New AquaLogic Service Bus Configuration Project wizard

Use this wizard to create an ALSB configuration project. For configuration options, see [ALSB Configuration page](#).

## ALSB Configuration page

An ALSB configuration project is a grouping of ALSB projects and resources destined for a server, a location for system resources (SMTP, UDDI, and such), and a container for validation; for example, a resource in a project associated with one ALSB configuration cannot refer to a resource in a project associated to another ALSB configuration.

Use this page to create a new ALSB configuration project (in the New AquaLogic Service Bus Configuration Project wizard) or to configure an existing one (in the Properties for ALSB Configuration editor).

The preserve, session, and customization file settings are used when publishing an ALSB configuration to the server, and used as defaults when configuring the [Export wizard - Export to Server - Select Resources page](#).

Option	Description
Configuration name	Enter a name for this ALSB configuration or keep the default.
<b>Advanced Options</b>	
Preserve environment variable values	Select this check box when you are re-importing a resource but want to preserve environment variable values in the existing resource.
Preserve security and policy settings	Select this check box to preserve the security configuration (excluding access control policies) and the references to the WS-policies bound directly to the service (instead of bound to the WSDL).
Preserve credentials (user name and password)	Select this check box to preserve PKI credentials in service key providers, user name and passwords in service accounts, and user name and password credentials in SMTP servers, JNDI providers, and UDDI registries.
Discard session if activation fails	Select this check box to discard the session if the activation fails (for example, due to conflicts). For more information, see <a href="#">Activating Sessions in Using the AquaLogic Service Bus Console</a> .
Session Name	The session name.
Description	The session description.
Deployment customization file	Specify a <i>customization.xml</i> file or click <b>Browse</b> , locate the file, then click <b>Open</b> . For information on customization, see <a href="#">Creating Customization Files</a> in <i>Using the AquaLogic Service Bus Console</i> .

Option	Description
Keystore file	Specify a <i>keystore.jks</i> file or click <b>Browse</b> , locate the file, then click <b>Open</b> .  The key store settings are used when configuring a service key provider.
Password	Enter the password that you use to secure access to the key store.
Server	The name of the server associated with this ALSB configuration. This setting is automatically configured unless there is more than one server from which to choose. When multiple servers are associated with the same ALSB configuration, use the drop-down list to select the server you want to associate with this ALSB configuration.  The server setting is only used for transport specific configuration, when the transport benefits from being connected to a server (for example, when configuring the dispatch policy setting in the HTTP transport).

## New AquaLogic Service Bus Project wizard

Use this page to create a new ALSB project.

Option	Description
Project name	Enter a unique name for the project. For more information, see <a href="#">Naming Projects and Folders</a> in <i>Using the AquaLogic Service Bus Console</i> .
Project contents	Select the <b>Use default</b> check box to keep the project in the default location or click <b>Browse</b> and select a folder.
ALSB Configuration	Select an existing ALSB configuration or click <b>New</b> to open the <a href="#">New AquaLogic Service Bus Configuration Project wizard</a> , where you can create a new configuration.

## Custom Resources

You can define custom resources for use by ALSB using the New Custom Resource wizard and the Custom Resource editor, as described in the following topics:

- [New Custom Resource wizard](#)

- [New Custom Resource wizard](#)
- [New Custom Resource - Resource Type page](#)

## New Custom Resource wizard

Use this wizard to create a new custom resource.

## New Custom Resource Editor

Use this editor to modify the configuration of a custom resource. The General page identifies the type of custom resource. The Custom page provides options for editing the configuration for that type of custom resource.

## New Custom Resource - Resource Type page

Use this page to select the type of custom resource to create. Select the type of custom resource to create from the list of available resource type.

## Custom MQ Resource Configuration page

Use this page to configure a custom MQ connection resource. For information on MQ connection resources and MQ transports, see the following:

- [MQ Connections](#) in *Using the AquaLogic Service Bus Console*
- [Native MQ Transport User Guide](#)

Option	Description
Connection Type	Select one of the following modes for connecting to the MQ queue manager: <ul style="list-style-type: none"><li>• <code>tcp mode</code>—Use TCP/IP to connect to a queue manager that does not reside on the same machine as ALSB.</li><li>• <code>binding mode</code>—Use the bindings mode to connect to a queue manager that is located on the same machine as ALSB.</li></ul>
MQ Host Name	For <code>tcp mode</code> connections only: Enter the host name of the MQ queue manager.

Option	Description
MQ Port Number	For <code>tcp</code> mode connections only: Enter the port number of the MQ queue manager listener.
MQ Queue Manager Name	Enter the name of the MQ queue manager to which to connect.
Queue Manager CCSID	For <code>tcp</code> mode connections only: The coded character set identifier (CCSID) to be used when establishing a connection. The CCSID is used mainly for internationalization support. To learn more, see IBM's <a href="#">WebSphere MQ Fundamentals</a> .
MQ Queue Manager Channel Name	For <code>tcp</code> mode connections only: Enter the queue manager server connection channel name.
SSL Required	For <code>tcp</code> mode connections: Select the check box to use SSL for sending messages. Only server-side SSL will be enabled when the <b>2-way SSL Required</b> option is <i>not</i> selected.
Cipher Suite	This option is available only when the <b>SSL Required</b> check box is selected. Select the Cipher Suite algorithm to be used by SSL. The Cipher Suite algorithm is used to encrypt and decrypt message communications between the WebSphere MQ server and the WebSphere MQ client. Thus a Cipher Suite algorithm must be specified when using SSL to communicate with a WebSphere MQ server.
2-way SSL Required	This option is available only when the <b>SSL Required</b> check box is selected. Select the check box to enable both client-side and server-side SSL authentication.
Reference to the Service Key Provider	If you selected <b>2-way SSL Required</b> , you must provide a reference to the service key provider for obtaining the appropriate key store and trust store information. Enter the path ( <code>project/folder</code> ) and name of a service key provider, or click <b>Browse</b> to select one from the Select Service Key Provider page.

Option	Description
Reference to the Static Service Account	For <code>tcp</code> mode connections only: Required for user name and password authentication. Enter the path ( <code>project/folder</code> ) and name of a static service account, or click <b>Browse</b> to select service accounts from a browser.
WebSphere MQ Version	Select the WebSphere MQ version: <ul style="list-style-type: none"> <li>• 5.3</li> <li>• 6.0</li> </ul>
Connection Pool Size	Enter the size of the MQ connection pool.
Connection Timeout	Enter the time interval in seconds after which unused connections are destroyed.

## Export wizard

The Export wizard contains the following pages:

- [“Export wizard - ALSB Configuration JAR Export page”](#) on page 3-36
- [“Export wizard - Export to Server - Select Resources page”](#) on page 3-37
- [“Export wizard - Export to Server - Review Resources page”](#) on page 3-38

### Export wizard - ALSB Configuration JAR Export page

Use this page to export ALSB resources to a configuration JAR file. For more information, see [Exporting Resources](#) in *Using the AquaLogic Service Bus Console*.

Option	Description
ALSB Configuration	Select an existing ALSB configuration and resources to export.
Export Level	Select whether to export projects or resources.  <b>Note:</b> A <b>System</b> project cannot be exported at the project level.  <b>Note:</b> Exporting projects might cause resource deletion when you import the full project JAR file. For more information, see <a href="#">Importing Resources</a> in <i>Using the AquaLogic Service Bus Console</i> .
Include Dependencies	If you selected to export resources, select or clear this check box. Use the <b>Include Dependencies</b> option to export any other resources that this resource references
Export Destination	Enter the fully qualified name of a JAR file to export, or click <b>Browse</b> to select it.

## Export wizard - Export to Server - Select Resources page

Use this page to select the projects or resources you want to export. Clear the check boxes next to any resources that you do not want to include in this export.

Option	Description
Resource	The name of the project and resource.
Operation	Create or update. The operation that will be performed on the resource.
Include Dependencies	Select this check box if you are exporting resources (not projects) and want to ensure that all the associated resources are exported.
<b>Preserve Environment Settings</b>	
Preserve environment variable values	Select this check box when you want to preserve (protect against overwriting) the environment variables values in the resource you are exporting.

Option	Description
Preserve security and policy settings	Select this check box to preserve the security configuration (excluding access control policies) and the references to the WS-policies bound directly to the service (instead of bound to the WSDL).
Preserve credentials (user name and password)	Select this check box to preserve PKI credentials in service key providers, user name and passwords in service accounts, and user name and password credentials in SMTP servers, JNDI providers, and UDDI registries.
<b>Session Settings</b>	
Activate session after publish	Select this check box to create and activate a session in the ALSB console. For more information, see <a href="#">Activating Sessions</a> in <i>Using the AquaLogic Service Bus Console</i> .
Discard session if activation fails	Select this check box to discard the session if the activation fails (for example, due to conflicts).
Description	The session description.
<b>Customization File</b>	Specify a customization file or click <b>Browse</b> , locate the file, then click <b>Open</b> . For information on customization, see <a href="#">Creating Customization Files</a> in <i>Using the AquaLogic Service Bus Console</i> .

## Export wizard - Export to Server - Review Resources page

Use this page to select the projects or resources you want to export.

Option	Description
ALSB Configuration	Select an existing ALSB configuration and resources to export.
Export Level	Select whether to export projects or resources.
Server	From the drop-down list, select an ALSB destination server.
Session	The session name.

## Import wizard

The Import wizard has the following pages:

- “Import wizard - Config JAR Import - Load Resources page” on page 3-39
- “Import wizard - Config JAR Import - Review Resources page” on page 3-39
- “Import wizard - Config ZIP Import - Load Resources page” on page 3-40
- “Import wizard - Config ZIP Import - Review Resources page” on page 3-41
- “Import wizard - URL Import - Load Resources page” on page 3-41
- “Import wizard - URL Import - Review Resources page” on page 3-41

## Import wizard - Config JAR Import - Load Resources page

Use this page to select a configuration JAR to import and an import destination. For more information, see *Importing Resources* in *Using the AquaLogic Service Bus Console*.

Option	Description
ALSB Configuration	Select an existing ALSB configuration or click <b>New</b> to open the <a href="#">New AquaLogic Service Bus Configuration Project wizard</a> , where you can create a new configuration.
Jar	Select a full project JAR file or a resource JAR file that has been previously exported from another ALSB domain.

## Import wizard - Config JAR Import - Review Resources page

Use this page to select the objects on which you want to operate (create, update, or delete). Resources are only scheduled for deletion when the JAR being imported is a full project JAR and there are project resources in the importing system that are not present in the imported JAR file. To prevent resources from being deleted, deselect them. For more information, see *Importing Resources* in *Using the AquaLogic Service Bus Console*.

Option	Description
Resources	The name of the project and resource.
Operation	Expand the Project folder to display the operations (create, update, delete) that will be performed on the resources.  To prevent resources from being deleted, deselect them. Resources are only scheduled for deletion when the JAR being imported is a full project JAR and there are project resources in the importing system that are not present in the imported JAR file.
Include Dependencies	Select this check box if you are importing a resource JAR file and want to ensure that all its associated resources are imported.
Passphrase	Enter the password that was used to encrypt the data.
<b>Preserve Environment Settings</b>	
Preserve environment variable values	Select this check box when you are re-importing a resource but want to preserve environment variable values in the existing resource.
Preserve security and policy settings	Select this check box to preserve the security configuration (excluding access control policies) and the references to the WS-Policies bound directly to the service (instead of bound to the WSDL).
Preserve credentials (user name and password)	Select this check box to preserve PKI credentials in service key providers, user name and passwords in service accounts, and user name and password credentials in SMTP servers, JNDI providers, and UDDI registries.

## Import wizard - Config ZIP Import - Load Resources page

Use this page to select a ZIP file with resources to import and an import destination. For more information, see [Loading Resources from a Zip File](#) in *Using the AquaLogic Service Bus Console*.

Option	Description
ALSB Configuration	Select an existing ALSB configuration and an import destination (project or folder).
File Name	Enter the fully qualified name of a ZIP file to import, or click <b>Browse</b> to select it.

## Import wizard - Config ZIP Import - Review Resources page

Use this page to select the objects you want to import. Clear the check boxes next to any resources that you do not want to include in this import. For more information, see [Loading Resources from a Zip File](#) in *Using the AquaLogic Service Bus Console*.

Option	Description
Resource	The name of the project and resource.
Operation	Create or update. The operation that will be performed on the resource.
File Name	The file name of the resource, including the file extension.

## Import wizard - URL Import - Load Resources page

Use this page to import resources such as WSDLs or XML schemas that are available on the Web. You can import them, along with all their dependents, by specifying the URL of the root resource. For more information, see [Loading Resources from a URL](#) in *Using the AquaLogic Service Bus Console*.

Option	Description
ALSB Configuration	Select an existing ALSB configuration and an import destination (project or folder).
URL	Enter the URL where the file is located.  To specify a local resource, you can use the file protocol with a file name fully qualified by its path, for example, <code>file:///c:/alsbresources/ForEachAction.jar</code> .
Resource Name	Enter a name for the resource.
Resource Type	Select the type of resource from the list.

## Import wizard - URL Import - Review Resources page

Use this page to select the objects you want to import. Clear the check boxes next to any resources that you do not want to include in this import. For more information, see [Loading Resources from a URL](#) in *Using the AquaLogic Service Bus Console*.

Option	Description
Resource	The name of the project and resource.
Operation	Create or update. The operation that will be performed on the resource.
URL	Enter the URL where the file is located.  To specify a local resource, you can use the file protocol with a file name fully qualified by its path, for example, <code>file:///c:/alsbresources/ForeachAction.jar</code> .

## JNDI Providers

The following are provided for working with JNDI providers:

- [JNDI Provider Editor](#)
- [New JNDI Provider Resource wizard](#)

### JNDI Provider Editor

Use this editor to modify an existing JNDI provider configuration. For descriptions of the fields, see the [New JNDI Provider Resource wizard](#). For more information, see [Editing JNDI Providers](#) in *Using the AquaLogic Service Bus Console*.

### New JNDI Provider Resource wizard

Use this page to configure a new JNDI provider resource. For more information, see [Adding JNDI Providers](#) in *Using the AquaLogic Service Bus Console*.

Option	Description
Description	Enter a description for the JNDI provider.
JNDI Cache	Keep the default <b>Enabled</b> option or select <b>Disabled</b> .  When enabled, the JNDI context and JNDI objects are cached locally which improves performance when doing an object lookup. BEA recommends that you keep the JNDI cache enabled.

Option	Description
Provider URL	Enter the URL for the JNDI provider in the format: protocol://host:port  You can use any protocol, for example, <code>http</code> , <code>https</code> , <code>t3</code> , <code>t3s</code> , <code>iiop</code> , <code>iiops</code> .
User Name	If access to the target JNDI provider requires a user name and password, enter a user name in the <b>User Name</b> field, and the associated password in the <b>Password</b> and <b>Confirm Password</b> fields.  These fields are optional, and required only if the JNDI tree is secured.
Password	Enter the associated password.
Confirm Password	Enter the same password you entered for the <b>Password</b> field.

## Message Flow Design Palette

The Message Flow Design Palette lists all the nodes and actions you can use to construct a message flow for a proxy service. To insert a node or an action into a message flow, drag the item from the palette to the [Message Flow Editor](#). When you drag an item to the palette, one or more targets appear (  ) to indicate that you can drop the dragged item in that position on the palette.

When you drag the item onto a target, the target is highlighted (  ) to show that you can drop the item there.

You can also add nodes and actions to message flows by right-clicking an object in the Message Flow Editor and choosing a node or action from the **Insert**, **Insert Into**, or **Insert After** submenus. You can also add an error handler by selecting the **Add Error Handler** command. These submenus and commands are context sensitive. That is, they appear only when it is legal to add the item into the selected context in the message flow.

The Message Flow Design Palette is organized into the following categories:

- “Message Flow Nodes” on page 3-44
- “Message Flow Route Actions - Communication Actions” on page 3-44
- “Message Flow Route Actions - Flow Control Actions” on page 3-45
- “Message Flow Stage Actions - Communication Actions” on page 3-45

- [“Message Flow Stage Actions - Flow Control Actions”](#) on page 3-46
- [“Message Flow Stage Actions - Message Processing Actions”](#) on page 3-47
- [“Message Flow Stage Actions - Reporting Actions”](#) on page 3-48

## Message Flow Nodes

The following table describes the nodes you can add to a message flow:

Node	Description
Conditional branch	A branch node allows processing to proceed down exactly one of several possible paths. For configuration properties, see <a href="#">Conditional Branch Node Properties</a> .
Operational branch	An operational branch node determines what branch to follow based on specified operations. For configuration properties, see <a href="#">Operational Branch Node Properties</a> .
Pipeline pair	A pipeline pair node consists of a request pipeline and a response pipeline. For configuration properties, see <a href="#">Pipeline Pair Node Properties</a> .
Route	Route node actions define the handling of messages as they flow through the route node. For configuration properties, see <a href="#">Route Node Properties</a> .
Stage	A stage node is a container of actions. For configuration properties, see <a href="#">Stage Node Properties</a> .
Error handler	An error handler provides the logic for resending errors in the message flow. For configuration properties, see <a href="#">Error Handler Node Properties</a> .

## Message Flow Route Actions - Communication Actions

The following table describes the communication actions you can add to a route in a message flow:

Action	Description
Dynamic routing	A dynamic routing action assigns a route for a message based on routing information available in an XQuery resource. For configuration properties, see <a href="#">Dynamic Routing Action Properties</a> .
Routing	A routing action identifies a target service for the message and configures how the message is routed to that service: For configuration properties, see <a href="#">Routing Action Properties</a> .
Routing table	A routing table action assigns a set of routes wrapped in a switch-style condition table. Different routes are selected based upon the results of a single XQuery expression. For configuration properties, see <a href="#">Routing Table Action Properties</a> .

## Message Flow Route Actions - Flow Control Actions

The following table describes the flow control action you can add to a route in a message flow:

Action	Description
If-then	An if-then action performs an action or a set of actions conditionally, based on the Boolean result of an XQuery expression. For configuration properties, see <a href="#">If-Then Action Properties</a> .

## Message Flow Stage Actions - Communication Actions

The following table describes the communication actions you can add to a stage in a message flow:

Action	Description
Dynamic Publish	A dynamic publish action publishes a message to a service identified by an XQuery expression For configuration properties, see <a href="#">Dynamic Publish Action Properties</a> .

Publish	A publish action publishes a message to a statically specified service. For configuration properties, see <a href="#">Publish Action Properties</a> .
Publish Table	A publish table action publishes a message to zero or more statically specified services. Switch-style condition logic is used to determine at run time which services will be used for the publish. For configuration properties, see <a href="#">Publish Table Action Properties</a> .
Routing Options	A routing options action modifies any or all of the following properties in the outbound request: URI, Quality of Service, Mode, Retry parameters, Message Priority. For configuration properties, see <a href="#">Routing Options Action Properties</a> .
Service Callout	A service callout action configures a synchronous (blocking) callout to an ALSB-registered proxy or business service. For configuration properties, see <a href="#">Service Callout Action Properties</a> .
Transport Headers	A transport header action sets the transport header values in messages For configuration properties, see <a href="#">Transport Headers Action Properties</a> .

## Message Flow Stage Actions - Flow Control Actions

The following table describes the flow control actions you can add to a stage in a message flow:

Action	Description
For-Each	A for-each action iterates over a sequence of values and executes a block of actions For configuration properties, see <a href="#">For-Each Action Properties</a> .
If-Then	An if-then action performs an action or set of actions conditionally, based on the Boolean result of an XQuery expression. For configuration properties, see <a href="#">If Action and Else-If Action Properties</a> .
Raise error	A raise-error action raises an exception with a specified error code (a string) and description. For configuration properties, see <a href="#">Raise Error Action Properties</a> .

Reply	A reply action specifies that an immediate reply be sent to the invoker. For configuration properties, see <a href="#">Reply Action Properties</a> .
Skip	A skip action specifies that at run time, the execution of the current stage is skipped and the processing proceeds to the next stage in the message flow. For configuration properties, see <a href="#">Skip Action Properties</a> .
Resume	A resume action resumes message flow after an error is handled by an error handler. For configuration properties, see <a href="#">Resume Action Properties</a> .

## Message Flow Stage Actions - Message Processing Actions

The following table describes the message processing actions you can add to a stage in a message flow:

Action	Description
Assign	An assign action assigns the result of an XQuery expression to a context variable. For configuration properties, see <a href="#">Assign Action Properties</a> .
Delete	A delete action deletes a context variable or a set of nodes specified by an XPath expression. For configuration properties, see <a href="#">Delete Action Properties</a> .
Insert	An insert action inserts the result of an XQuery expression at an identified place relative to nodes selected by an XPath expression. For configuration properties, see <a href="#">Insert Action Properties</a> .
Java callout	A Java callout action invokes a Java method from the pipeline. For configuration properties, see <a href="#">Java Callout Action Properties</a> .
MFL transform	A MFL transform action converts non-XML to XML or XML to non-XML in the pipeline. For configuration properties, see <a href="#">MFL Transform Action Properties</a> .

Rename	A rename action renames elements selected by an XPath expression without modifying the contents of the element. For configuration properties, see <a href="#">Rename Action Properties</a> .
Replace	A replace action replaces a node or the contents of a node specified by an XPath expression. For configuration properties, see <a href="#">Replace Action Properties</a> .
Validate	A validate action validates elements selected by an XPath expression against an XML schema element or a WSDL resource. For configuration properties, see <a href="#">Validate Action Properties</a> .

## Message Flow Stage Actions - Reporting Actions

The following table describes the reporting actions you can add to a stage in a message flow:

Action	Description
Alert	An alert action ends an alert notification based on pipeline message context. For configuration properties, see <a href="#">Alert Action Properties</a> .
Log	A log action constructs a message to be logged. For configuration properties, see <a href="#">Log Action Properties</a> .
Report	A report action enables message reporting for a proxy service. For configuration properties, see <a href="#">Report Action Properties</a> .

## Message Flow Editor

Use this editor to construct a proxy service message flow. To insert a node or an action into a message flow, drag the item from the [Message Flow Design Palette](#) to the editor. When you drag

an item to the editor, one or more targets appear (  ) to indicate that you can drop the dragged item in that position on the palette. When you drag the item onto a target, the target is highlighted

(  ) to show that you can drop the item there.

You can also add nodes and actions to message flows by right-clicking an object in the Message Flow Editor and choosing a node or action from the **Insert**, **Insert Into**, or **Insert After** submenus. You can also add an error handler by selecting the **Add Error Handler** command. These submenus and commands are context sensitive. That is, they appear only when it is legal to add the item into the selected context in the message flow.

When you select a node or action in the editor, a configuration page for that item is displayed in the Properties view. You can add or modify configuration properties in those pages. The message flow node and action properties configuration pages are:

- [“Alert Action Properties” on page 3-50](#)
- [“Message Flow Properties- Comment” on page 3-65](#)
- [“Assign Action Properties” on page 3-52](#)
- [“Conditional Branch Node Properties” on page 3-53](#)
- [“Conditional Branch Node Properties” on page 3-53](#)
- [“Delete Action Properties” on page 3-54](#)
- [“Dynamic Publish Action Properties” on page 3-55](#)
- [“Dynamic Routing Action Properties” on page 3-56](#)
- [“Error Handler Node Properties” on page 3-57](#)
- [“Error Handler Node Properties” on page 3-57](#)
- [“For-Each Action Properties” on page 3-58](#)
- [“If Action and Else-If Action Properties” on page 3-60](#)
- [“If-Then Action Properties” on page 3-59](#)
- [“Insert Action Properties” on page 3-61](#)
- [“Java Callout Action Properties” on page 3-62](#)
- [“Log Action Properties” on page 3-64](#)
- [“MFL Transform Action Properties” on page 3-66](#)
- [“Message Flow Properties - Namespaces” on page 3-66](#)
- [“Operational Branch Node Properties” on page 3-67](#)

- [“Pipeline Pair Node Properties”](#) on page 3-68
- [“Publish Action Properties”](#) on page 3-69
- [“Publish Table Action Properties”](#) on page 3-70
- [“Raise Error Action Properties”](#) on page 3-72
- [“Rename Action Properties”](#) on page 3-73
- [“Replace Action Properties”](#) on page 3-74
- [“Reply Action Properties”](#) on page 3-75
- [“Report Action Properties”](#) on page 3-76
- [“Resume Action Properties”](#) on page 3-78
- [“Route Node Properties”](#) on page 3-78
- [“Routing Action Properties”](#) on page 3-79
- [“Routing Options Action Properties”](#) on page 3-80
- [“Routing Table Action Properties”](#) on page 3-82
- [“Service Callout Action Properties”](#) on page 3-83
- [“Skip Action Properties”](#) on page 3-89
- [“Stage Node Properties”](#) on page 3-89
- [“Transport Headers Action Properties”](#) on page 3-90
- [“Validate Action Properties”](#) on page 3-94
- [“Message Flow Properties - Variables”](#) on page 3-66

## Alert Action Properties

In a message flow, use the alert action to generate alerts based on message context in a pipeline, to send to an alert destination. Unlike SLA alerts, notifications generated by the alert action are primarily intended for business purposes, or to report errors, and not for monitoring system health. Alert destinations should be configured and chosen with this in mind. To learn more about alert destinations, see [“Alert Destination editor”](#) on page 3-1.

If pipeline alerting is not enabled for the service or at the domain level, the configured alert action is bypassed during message processing.

In the [Message Flow Editor](#), click an alert action to display its properties in the Properties view. Use these properties pages to configure the selected alert action. The pages are:

- Alert
- Comment
- Namespaces
- Variables

The Alert page has the following options:

Option	Description
Expression	An XQuery expression that specifies the message context to be added to the alert message.  To create or edit an expression, click <b>&lt;Expression&gt;</b> (or the <i>expression fragment</i> , if one is already defined) to display the <a href="#">XQuery/XSLT Expression Editor</a> .
Summary	A short description of the alert. This will be the subject line in the case of an e-mail notification and can contain no more than 80 characters. If no description is provided, a predefined subject line that reads, “ALSB Alert,” will be used instead.
Severity	The severity level for this alert. Select a level from the list.
Destination	The destination for the alert. To specify a destination, click <b>Browse</b> to select an appropriate resource.

**Tip:** To prevent exceptions from aborting the message being processed when generating a pipeline alert, it is recommended that an error handler for the alert action be defined to handle and contain such exceptions locally, rather than having them bubble up to a global error handler.

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Assign Action Properties

In a message flow, use an assign action to assign the result of an XQuery expression to a context variable.

In the [Message Flow Editor](#), click an assign action to display its properties in the Properties view. Use these properties pages to configure the selected assign action. The pages are:

- Assign
- Comment
- Namespaces
- Variables

The Assign page has the following options:

Option	Description
Expression	An expression that creates the data that is assigned to variable named in the <b>Variable</b> field, described below.  To create or edit an expression, click <b>&lt;Expression&gt;</b> (or the <b><i>expression_fragment</i></b> , if one is already defined) to display the <a href="#">XQuery/XSLT Expression Editor</a> .
Variable	The variable to which the value created in the XQuery expression described above is assigned.

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Conditional Branch Node Properties

In a message flow, use a conditional branch node to specify that message processing is to proceed along exactly one of several possible paths, based on a result returned by an XPath condition.

Conditional branching is driven by a lookup table with each branch tagged with a simple, but unique, string value. A variable in the message context is designated as the lookup variable for that node, and at run time, its value is used to determine which branch to follow. If no branch matches the value of the lookup variable, the default branch is followed. You should design the proxy service in such a way that the value of the lookup variable is set before reaching the branch node.

In the [Message Flow Editor](#), click a conditional branch node to display its properties in the Properties view. Use these properties pages to configure the selected conditional branch node. The pages are:

- Flow
- Conditional Branch

The Flow page has the following options:

Option	Description
Name	Enter a name for the conditional branch node.
Description	Enter a description for the conditional branch node.

The Conditional Branch page has the following options:

Option	Description
XPath	The XPath expression that defines the condition to be evaluated for determining the branch to follow.  To create or edit the XPath expression, click <XPath> (or the <i>XPath fragment</i> , if one is already defined) to display the <a href="#">XPath Expression Editor</a> .
Variable	Enter a context variable.

A conditional branch node also always contains one or more branches, which are configured as part of the node.

Click a **Branch** icon in a conditional branch node to display the Branch properties page in the Properties view. Use these properties pages to configure the selected branch node in a message flow. This page has the following options.

Option	Description
Label	A label for the branch. This label appears as the label for the branch in the Message Flow Editor.
Operator	Select an operator from the list to be used with the value in the next field, for creating the condition on which the branch is based.
Value	Enter a value to be used with the operator in the previous field, for creating the condition

## Delete Action Properties

In a message flow, use a delete action to delete a context variable or a set of nodes specified by an XPath expression.

In the [Message Flow Editor](#), click a delete action to display its properties in the Properties view. Use these properties pages to configure the selected delete action. The pages are:

- Delete
- Comment
- Namespaces
- Variables

The Delete page has the following options. Select **Variable** to delete a variable, or select **XPath** to delete an XPath expression.

Option	Description
Variable	Select this radio button to delete a context variable. Enter the name of the context variable to delete in the adjacent text field.
XPath	<p>Select this radio button to delete all nodes selected by an XPath expression. Then:</p> <ul style="list-style-type: none"> <li>• To create or edit the XPath expression, click <b>&lt;XPath&gt;</b> (or the <b><i>xPath_fragment</i></b>, if one is already defined) to display the <a href="#">XPath Expression Editor</a>.</li> <li>• After saving the expression, in the <b>In Variable</b> field, enter the context variable containing the nodes specified in the XPath expression.</li> </ul>

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Dynamic Publish Action Properties

In a message flow, use a dynamic publish action to publish a message to a service specified by an XQuery expression.

In the [Message Flow Editor](#), click a dynamic publish action to display its properties in the Properties view. Use these properties pages to configure the selected dynamic publish action. The pages are:

- Dynamic Publish
- Comment
- Namespaces
- Variables

The Dynamic Publish page has the following options:

Option	Description
Service	<p>An XQuery expression that defines the service to which a message is to be published.</p> <p>To create or edit the expression, click <b>&lt;Expression&gt;</b> (or the <b><i>expression_fragment</i></b>, if one is already defined) to display the <a href="#">XQuery/XSLT Expression Editor</a>.</p> <p>In the editor, enter an XQuery expression or select an XQuery resource that provides a result similar to:</p> <pre>&lt;ctx:route isProxy="false"&gt;   &lt;ctx:service&gt;project/folder/businessservice&lt;     /ctx:service&gt;   &lt;ctx:operation&gt;foo&lt;/ctx:operation&gt; &lt;/ctx:route&gt;</pre> <p><b>Note:</b> The element <code>operation</code> is optional.</p>

Use the [Comment](#) page to add a comment, if desired:

Use the [Namespaces](#) page to see a list of defined namespaces or to create a new one.

Use the [Variables](#) page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Dynamic Routing Action Properties

In a message flow, use a dynamic routing action to assign a route for a message based on routing information available in an XQuery resource.

This is a terminal action, which means you cannot add another action after this one. However, this action can contain request and response actions.

In the [Message Flow Editor](#), click a dynamic routing action to display its properties in the Properties view. Use these properties pages to configure the selected dynamic routing action. The pages are:

- [Dynamic Routing](#)
- [Comment](#)

- Namespaces
- Variables

The Dynamic Routing page has the following option:

Option	Description
Service	<p>An XQuery expression that defines the route to be taken by a message.</p> <p>To create or edit an expression, click <b>&lt;Expression&gt;</b> (or the <b><i>expression_fragment</i></b>, if one is already defined) to display the <a href="#">XQuery/XSLT Expression Editor</a>.</p> <p>In the XQuery/XSLT Expression editor, enter an Xquery expression, the result of which is similar to:</p> <pre>&lt;ctx:route&gt;   &lt;ctx:service isProxy='true'&gt;{\$service}&lt;/ctx:service&gt;   &lt;ctx:operation&gt;{\$operation}&lt;/ctx:operation&gt; &lt;/ctx:route&gt;</pre> <p><b>Note:</b> If a proxy service is being invoked, <code>isProxy</code> attribute should be set to <code>true</code>.</p> <ul style="list-style-type: none"> <li>– The service name is the fully qualified service name.</li> <li>– The operation element is optional</li> </ul>

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Error Handler Node Properties

Use an error handler to specify what should happen if an error occurs in a specific location in the message flow.

All configuration for an error handler is in one or more stages contained by the error handler. See [Stage Node Properties](#).

## For-Each Action Properties

In a message flow, use the for-each action to iterate over a sequence of values and execute a block of actions.

In the [Message Flow Editor](#), click a for-each action to display its properties in the Properties view. Use these properties pages to configure the selected for-each action. The pages are:

- For Each
- Comment
- Namespaces
- Variables

The For Each page has the following options:

Option	Description
For Each Variable	Enter the name of the variable on whose contents the for-each action(s) will be executed.
XPath	An XPath expression that specifies where in the structure of the containing context variable the variable specified in the <b>For Each Variable</b> field is located.  To create or edit the XPath expression, click <XPath> (or the <i>XPath fragment</i> , if one is already defined) to display the <a href="#">XPath Expression Editor</a> .
In Variable	The context variable containing the variable on whose contents the for-each action(s) will be executed.
Index Variable	A variable containing the current number of iterations in the loop.
Count Variable	A variable containing the total number of iterations.

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## If-Then Action Properties

In a message flow, use an if-then action to perform an action or a set of actions conditionally, based on the Boolean result of an XQuery expression.

In the [Message Flow Editor](#), click an if-then action to display its properties in the Properties view. Use this page to review and configure general properties of the if-then action. The pages are:

- Comment
- Namespaces
- Variables

An if-then action always contains an if condition plus zero or more else-if condition, where you define the conditions for the if-then action. An if-then action also always contains an else condition, which defines the default path when no other condition is met.

Click an **If:condition** icon or an **Else-If:condition** icon in an if-then action to display their properties in the Properties view. Use these properties pages to configure the selected condition. This **If** condition properties page has the following option.

## If Action and Else-If Action Properties

If actions and else-if actions are always contained by an if-then action. The message follows the path associated with the first if action or else-if action that returns true.

Option	Description
Condition	<p>A condition in an if action or an if-else action that contains one of the tests for following alternative paths in the flow.</p> <p>To add or edit a condition,</p> <ol style="list-style-type: none"> <li>1. Click <b>&lt;Condition&gt;</b> (or <i>condition_fragment</i>, if one is already defined) to display the <a href="#">Condition Editor</a>. Define a condition to be evaluated in the if-then action.</li> <li>2. When you finish editing the condition, add one or more action that will be executed when the condition evaluates to true. To add an action, drag it from the <b>Design Palette</b> to associate with the condition.</li> </ol> <p>In the route node, you can select only the routing, dynamic routing, or routing table actions. However, these actions can contain request and response actions.</p> <ol style="list-style-type: none"> <li>3. To add an else-if condition, click <b>add condition</b>. Then add one or more actions to this else-if condition, as described above for the If condition. Continue with as many else-if conditions as your logic requires.</li> </ol> <p>Condition actions can be nested.</p>

## Else Action Properties

The else action does not have associate properties. When all if and else-if conditions return false, the message proceeds down the path associated with the else action.

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Insert Action Properties

In a message flow, use an insert action to insert the result of an XQuery expression at an identified place relative to nodes selected by an XPath expression.

In the [Message Flow Editor](#), click an insert action to display its properties in the Properties view. Use these properties pages to configure the selected insert action. The pages are:

- Insert
- Comment
- Namespaces
- Variables

The Insert page has the following options:

Option	Description
Expression	<p>The XQuery expression used to create the data that will be inserted at a specified location in a named variable.</p> <p>To create or edit an expression, click <b>&lt;Expression&gt;</b> (or the <i>expression_fragment</i>, if one is already defined) to display the <a href="#">XQuery/XSLT Expression Editor</a>.</p>
Location	<p>The location where the insert is performed, relative to the result of the XPath expression: Options are:</p> <ul style="list-style-type: none"> <li>• <b>Before</b>—as sibling before each element or attribute selected by the XPath expression</li> <li>• <b>After</b>—as sibling after each element or attribute selected by the XPath expression</li> <li>• <b>As first child of</b>—as first child of each element identified by the XPath expression. An error occurs if the result of the XPath returns attributes.</li> <li>• <b>As last child of</b>—as last child of each element identified by the XPath expression. An error occurs if the XPath returns attributes.</li> </ul>

Option	Description
XPath	<p>Valid configurations include those in which:</p> <ul style="list-style-type: none"> <li>• XQuery and XPath expressions both return elements.</li> <li>• The XQuery and XPath expressions both return attributes—in which case, the XQuery expression must return attributes.</li> </ul> <p>To create or edit the XPath expression, click <b>&lt;XPath&gt;</b> (or the <b><i>XPath_fragment</i></b>, if one is already defined) to display the <a href="#">XPath Expression Editor</a>.</p>
Variable	<p>The context variable whose contents are evaluated by the XPath variable defined above. Enter the name of the variable in the text field.</p>

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Java Callout Action Properties

In a message flow, use a Java callout action to invoke a Java method or an EJB business service from within the message flow.

In the [Message Flow Editor](#), click a Java callout action to display its properties in the Properties view. Use these properties pages to configure the selected Java callout action. The pages are:

- Java Callout
- Comment
- Namespaces
- Variables

The Java Callout page has the following options:

Option	Description
Method	<p>An external Java method to be called from the message flow.</p> <p>Click <b>Browse</b> to select a class and a static method from an archived resource. Once you have selected the class and method, a table appears on the <b>Java Callout Properties</b> page:</p> <p>The <b>Name</b> column lists all the method's arguments.</p> <p>The <b>Action</b> column provides an <b>&lt;Expression&gt;</b> or <i>expression_fragment</i> link to the <a href="#">XQuery/XSLT Expression Editor</a>, where you can create an expression to retrieve a value for the argument.</p> <p>Data types for the arguments must be one of the following:</p> <ul style="list-style-type: none"> <li>• <code>java.lang.String</code></li> <li>• Primitive types, and their corresponding class types (e.g., <code>int</code> vs. <code>java.lang.Integer</code>)</li> <li>• <code>java.lang.BigDecimal</code>, and <code>java.lang.BigInteger</code> (these types are used in financial calculations where round-off errors or overflows are not tolerable)</li> <li>• <code>org.apache.xbeans.XmlObject</code> and no typed xml beans.</li> <li>• <code>byte[]</code></li> <li>• <code>java.lang.String[]</code> (INPUT ONLY)</li> <li>• <code>XmlObject []</code> (INPUT ONLY)</li> </ul> <p>If the type of the input value you enter does not match the declared input argument type, ALSB tries to automatically typecast input values to the declared type of the input argument. For example a string value of "123" will be converted to integer 123 if the declared type of the input argument is java primitive <code>int</code>.</p>

Option	Description
Result Type	<p>The variable to which the result is assigned. The label for the field indicates the data type of the result.</p> <p>If the result is a byte array (the only possible array returned), the binary-content XML element is returned.</p>
Service Account	<p>An optional Service Account, which can be specified if there is a security context for this Java method.</p> <p>Click <b>Browse</b> to select a service account.</p> <p>In the case of fixed and mapped service accounts, the userid/password from the service account is authenticated in the local system and the security context propagated to the Java callout. In the case of <code>passthru</code>, the security context is propagated to the Java callout. This context is the message level context if defined (with WS-Security). Otherwise, it is the transport level context.</p>

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Log Action Properties

In a message flow, use the log action to construct a message to be logged and to define a set of attributes with which it will be logged.

In the [Message Flow Editor](#), click a log action to display its properties in the Properties view. Use these properties pages to configure the selected log action. The pages are:

- Log
- Comment
- Namespaces
- Variables

The Log page has the following options:

Option	Description
Expression	<p>The message context to be logged through XQuery expressions on context variables.</p> <p>To create or edit an expression, click &lt;<b>Expression</b>&gt; (or the <b>expression_fragment</b>, if one is already defined) to display the <a href="#">XQuery/XSLT Expression Editor</a>.</p>
Annotation	Notes for this log action. These notes are logged along with the result of the previously defined expression.
Severity	<p>The severity of the log message. Options are:</p> <p><b>Debug</b> - While your application is under development, you might find it useful to create and use messages that provide verbose descriptions of low-level activity within the application.</p> <p><b>Info</b> -Used for reporting normal operations; a low-level informational message.</p> <p><b>Warning</b> - A suspicious operation or configuration has occurred but it might not affect normal operation.</p> <p><b>Error</b> - A user error has occurred. The system or application can handle the error with no interruption and limited degradation of service.</p>

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Message Flow Properties- Comment

In the [Message Flow Editor](#), click a node or an action to display its properties in the Properties view. For most nodes and actions, one of the properties pages displayed (as a tab) is the Comment page. Use this page to add an optional comment about the item selected in the message flow.

## Message Flow Properties - Namespaces

In the [Message Flow Editor](#), click a node or an action to display its properties in the Properties view. For most nodes and actions, one of the properties pages displayed (as a tab) is the Namespaces page. Use this page to see a list of defined namespaces or to create a new namespace.

## Message Flow Properties - Variables

In the [Message Flow Editor](#), click a node or an action to display its properties in the Properties view. For many nodes and actions, one of the properties pages displayed (as a tab) is the Variables page. Use this page to see a list of all the predefined and user-defined context variables. Click **Add** to define a new variable.

For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## MFL Transform Action Properties

In a message flow, use a MFL (Message Format Language) transform action to convert message content from XML to non-XML, or vice versa, in the message pipeline. An MFL is a specialized XML document used to describe the layout of binary data. It is a BEA proprietary language used to define rules to transform formatted binary data into XML data, or vice versa.

In the [Message Flow Editor](#), click a MFL transform action to display its properties in the Properties view. Use these properties pages to configure the selected MFL transform action. The pages are:

- MFL Transform
- Comment
- Namespaces
- Variables

The MFL Transform page has the following options:

Option	Description
Apply Transform	The type of transform to be applied. Select <b>XML to Non-XML</b> or <b>Non-XML to XML</b> , according to your requirement.
on <Expression>	The variable on which the MFL transformation action is to be performed. Click < <b>Expression</b> > (or the <i>expression_fragment</i> , if one is already defined) to display the <a href="#">XQuery/XSLT Expression Editor</a> , where you can specify the variable.  This input must be text or binary when transforming to XML, and must be XML when transforming to non-XML. Binary content in the message context is represented by the binary-content XML element. This XML should be the result of the Xquery expression when the input needs to be binary.
Resource	Select this option to perform an MFL transform action using a static MFL resource. Click <b>Browse</b> to select the resource.
Resource From	Select this option to specify an MFL resource that will perform the transform action.  Click < <b>Expression</b> > (or the <i>expression_fragment</i> , if one is already defined) to display the <a href="#">XQuery/XSLT Expression Editor</a> , where you can specify the MFL resource that will perform the action, in the format <code>project/folder/MFLresourceName</code> .
Variable	The name of the variable to which the result of this transform action is to be assigned. The result will be a binary-content XML element.

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.


## Operational Branch Node Properties

In a message flow, use an operational branch node to configure branching based on operations defined in a WSDL.

When message flows define WSDL-based proxy services, operation-specific processing is required. Instead of configuring a branching node based on operations manually, ALSB provides a branching node that automatically branches based on operations. In other words, when you create an operational branch node in a message flow, you can quickly build your branching logic based on the operations defined in the WSDL, because the ALSB plug-in presents those operations in the operational branch node configuration page.

A branch node allows processing to proceed along exactly one of several possible paths. Branching is driven by an XPath-based switch table. Each branch in the table specifies a condition (for example, `<500`) that is evaluated in order down the message flow against a single XPath expression (for example, `./ns:PurchaseOrder/ns:totalCost on $body`). Whichever condition is satisfied first determines which branch is followed. If no branch condition is satisfied, then the default branch is followed. A branch node may have several descendants in the message flow: one for each branch, including the default branch.

When you add an operational branch node to a message flow in the [Message Flow Editor](#), the node contains an initial conditional branches based on the first operation defined in the WSDL, as shown below, plus a default branch:



Click the node itself (the **Operational Branch Node** icon or the bounding box connected to the icon) to display the Flow properties page in the Properties view. You can provide a name and a description for the node on that page.

Click an operational branch icon to display the properties for that operational branch on the Operational Branch page. That page contains a drop-down list of all the operations defined in the WSDL. You can select a different operation for that branch. You can also click the plus sign in the operational branch node, in the Message Flow Editor, to add another operation branch.

After you have added all the branches, add nodes and stages to them to define the processing for each branch.

## Pipeline Pair Node Properties

In a message flow, use a pipeline pair node to define request and response processing.

Message flows can include zero or more pipeline pair nodes: request and response pipelines for the proxy service (or for the operations on the service), and error handler pipelines that can be defined for stages, pipelines, and proxy services. Pipelines can include one or more stages, which in turn include actions.

A pipeline pair always contains a request pipeline and a response pipeline. Add stages and actions to those pipelines, as needed.

In the [Message Flow Editor](#), click a pipeline pair node to display its properties in the Properties view. Use this properties page to configure the selected pipeline pair node. The options are:

Option	Description
Name	Enter a name for the pipeline pair node.
Description	Enter a description for the pipeline pair node.

## Publish Action Properties

In a message flow, use a publish action to identify a statically specified target service for a message and to configure how the message is packaged and sent to that service.

In the [Message Flow Editor](#), click a publish action to display its properties in the Properties view. Use these properties pages to configure the selected publish action. The pages are:

- Publish
- Comment
- Namespaces
- Variables

The Publish page has the following options:

Option	Description
Service	The target service for the publish action. Click <b>Browse</b> to select a proxy service or business service from a list.
Invoking	The operation to be invoked on the target service. This option appears only if the selected service defines any operations. To configure how the message is packaged and sent to the service, in the <b>Request Actions</b> field, click <b>Add an Action</b> . Then select an action to associate with the service. You can add more than one action.
Use inbound operation for outbound	Select this option to make the outbound operation the same as the inbound operation. This option appears only if the selected service defines any operations.

Use the Comment page to add a comment, if desired:


Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Publish Table Action Properties

In a message flow, use a publish table action to publish a message to zero or more statically specified services. Switch-style condition logic is used to determine at run time which services will be used for the publish. A publish table action contains one or more case actions to define conditions for following alternative paths (by default, via publish actions), as well as a default path to a default publish action. To fully define a publish table action, you must configure the publish table action, its case actions, and its publish actions (and any other actions you may add).

When you add a publish table action to a message flow in the [Message Flow Editor](#), the publish table action contains a case action with a path to a publish action plus a default case action with a path to a default publish action, as shown below. Click **add condition** to add another condition to the publish table.



## Publish Table Properties

In the Message Flow Editor, click the publish table action itself (the **Publish Table** icon or the bounding box connected to the icon) to display the Publish Tables properties page in the Properties view. Use these properties pages to configure the selected publish table action. The pages are:

- Publish Table
- Comment
- Namespaces
- Variables

The Publish Table properties page has the following option:

Option	Description
Expression	<p>An XQuery expression, which at run time returns the value upon which the routing decision will be made.</p> <p>To create or edit an XQuery expression, click <b>&lt;Expression&gt;</b> (or the <b>expression_fragment</b>, if one is already defined) to display the <a href="#">XQuery/XSLT Expression Editor</a>.</p>

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Case Action Properties

In the Message Flow Editor, click a case action to display its properties in the Properties view. Use this properties page to configure the selected case action, as described below:

Option	Description
<ul style="list-style-type: none"> <li>Operator</li> <li>Value</li> </ul>	Select a comparison operator from the list. Then enter a value against which the value returned from the XQuery expression defined for the publish table action will be evaluate

## Publish Action Properties

See [Publish Action Properties](#).

## Raise Error Action Properties

In a message flow, use the raise error action to raise an exception with a specified error code (a string) and description.

In the [Message Flow Editor](#), click a raise error action to display its properties in the Properties view. Use these properties pages to configure the selected raise error action. The pages are:

- Raise Error
- Comment
- Namespaces
- Variables

The Raise Error page has the following options:

Option	Description
Code	The error code to be raised.
Message	Description of the error code

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Rename Action Properties

In a message flow, use the rename action to rename elements selected by an XPath expression without modifying the contents of the element.

In the [Message Flow Editor](#), click a rename action to display its properties in the Properties view. Use these properties pages to configure the selected rename action. The pages are:

- Rename
- Comment
- Namespaces
- Variables

The Rename page has the following options:

Option	Description
XPath	An XPath expression used to specify the data (in the named variable) that will be renamed.  To create or edit the XPath expression, click <b>&lt;XPath&gt;</b> (or the <b><i>xPath_fragment</i></b> , if one is already defined) to display the <a href="#">XPath Expression Editor</a> .
In Variable	The context variable that holds the element you want to rename. Enter the name of the variable in this field.
Localname	A local name to use to rename the selected elements. Enter the local name in this field.
Namespace	A namespace to use when renaming the selected elements. Enter the namespace in this field.

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Replace Action Properties

In a message flow, use a replace action to replace a node or the contents of a node specified by an XPath expression. The node or its contents are replaced with the value returned by an XQuery expression.

A replace action can be used to replace simple values, elements and even attributes. An XQuery expression that returns nothing is equivalent to deleting the identified nodes or making them empty, depending upon whether the action is replacing entire nodes or just node contents.

In the [Message Flow Editor](#), click a replace action to display its properties in the Properties view. Use these properties pages to configure the selected replace action. The pages are:

- Replace
- Comment
- Namespaces
- Variables

The Replace page has the following options:

Option	Description
XPath	The XPath expression used to specify the data (in the named variable) that will be replaced.  To create or edit the XPath expression, click <b>&lt;XPath&gt;</b> (or the <b><i>XPath fragment</i></b> , if one is already defined) to display the <a href="#">XPath Expression Editor</a> .
Variable	Enter a context variable.

Option	Description
Expression	<p>The XQuery expression used to create the data that replaces the data specified by the XPath in the named variable.</p> <p>To create or edit an expression, click <b>&lt;Expression&gt;</b> (or the <i><b>expression_fragment</b></i>, if one is already defined) to display the <a href="#">XQuery/XSLT Expression Editor</a>.</p>
Replace entire node or Replace node contents	<p>When you finish editing the XQuery expression, select one of the options:</p> <ul style="list-style-type: none"> <li>• <b>Replace entire node</b>—to specify that the nodes selected by the XPath expression you defined are replaced along with all of its contents</li> <li>• <b>Replace node contents</b>—to specify that the node is not replaced; only the contents are replaced.</li> </ul> <p><b>Note:</b> Selecting the <b>Replace node contents</b> option and leaving the <b>XPath</b> field blank is more efficient than selecting the <b>Replace entire node</b> option and setting the XPath to <code>./*</code></p>

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Reply Action Properties

In a message flow, use the reply action to specify that an immediate reply be sent to the invoker.

The reply action can be used in the request, response or error pipeline. You can configure it to result in a reply with success or failure. In the case of reply with failure where the inbound transport is HTTP, the reply action specifies that an immediate reply is sent to the invoker.

In the [Message Flow Editor](#), click a reply action to display its properties in the Properties view. Use these properties pages to configure the selected reply action. The pages are:

- Assign
- Comment
- Namespaces

- Variables

The Reply page has the following options:

Option	Description
With Success or With Failure	Select <b>With Success</b> to reply that the message was successful, or select <b>With Failure</b> to reply that the message has a fault.

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Report Action Properties

In a message flow, use the report action to enable message reporting for a proxy service.

In the [Message Flow Editor](#), click a report action to display its properties in the Properties view.

Use these properties pages to configure the selected report action. The pages are:

- Report
- Comment
- Namespaces
- Variables

The Report page has the following option:

Option	Description
Expression	<p>The XQuery expression used to create the data that will be reported.</p> <p>To create or edit an expression, click <b>&lt;Expression&gt;</b> (or the <i>expression_fragment</i>, if one is already defined) to display the <a href="#">XQuery/XSLT Expression Editor</a>.</p>
Search Keys	<p>When you finish editing the XQuery expression, click <b>Add a Key</b> to add one or more key value pairs to be used to extract key identifiers from any message context variable or message payload. (The rest of the message is ignored.) The keys are a convenient way to identify a message.</p> <ol style="list-style-type: none"> <li>1. In the <b>Key Name: Name</b> field enter a name for the key.</li> <li>2. In the <b>Key Value</b> column, click <b>&lt;XPath&gt;</b> to create the XPath expression in the <a href="#">XPath Expression Editor</a>.</li> <li>3. In the <b>In variable</b> field, enter the name of the variable on which the expression will be executed.</li> </ol>

For example, consider a report action configured on an error handler in a stage. The action reports the contents of the fault context variable in the event of an error. The report action is configured as follows:

- Key name = `errorCode`
- Key value = `./ctx:errorCode` in variable `fault`

Each time this action is executed at run time, a message is reported via the Reporting Data Stream. The following table shows the results after the report action is executed twice.

Report Index	DB TimeStamp	Inbound Service	Error Code
errorCode=BEA-382505	04/26/07 9:45 AM	MortgageBroker/ProxySvcs/loanGateway3	BEA-382505
errorCode=BEA-382505	04/26/07 9:45 AM		BEA-382505

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Resume Action Properties

In a message flow, use the resume action to resume message flow after an error is handled by an error handler. This action has no parameters and can only be used in error pipelines.

In the [Message Flow Editor](#), click a resume action to display its properties in the Properties view. Use these properties pages to configure the selected resume action. The pages are:

- Comment
- Namespaces
- Variables

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Route Node Properties

In a message flow, use the route node to handle request and response dispatching of messages to and from business services. No other nodes can follow a route node.

In the [Message Flow Editor](#), click a route node to display its properties in the Properties view. Use these properties pages to configure the selected route node. The pages are:

- Route
- Namespaces
- Variables

The Route page has the following option:

Option	Description
Name	Enter a name for the route node.
Description	Enter a description for the route node.

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Routing Action Properties

In a message flow, use a routing action to identify a target service for the message and configure how the message is routed to that service.

This is a terminal action, which means you cannot add another action after this one. However, this action can contain request and response actions.

In the [Message Flow Editor](#), click a routing action to display its properties in the Properties view. Use these properties pages to configure the selected routing action. The pages are:

- Routing
- Comment
- Namespaces
- Variables

The Routing page has the following option:

Option	Description
Service	The target service for the routing action. Click <b>Browse</b> to select a proxy service or business service from a list.
Invoking	The operation to be invoked on the target service. This option appears only if the selected service defines any operations. To configure how the message is packaged and sent to the service, in the <b>Request Actions</b> field, click <b>Add an Action</b> . Then select an action to associate with the service. You can add more than one action.
Use inbound operation for outbound	Select this option to make the outbound operation the same as the inbound operation. This option appears only if the selected service defines any operations.

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Routing Options Action Properties

In a message flow, use a routing options action to modify any or all of the following properties in the outbound request: URI, Quality of Service, Mode, Retry parameters, Message Priority.

In the [Message Flow Editor](#), click a routing options action to display its properties in the Properties view. Use these properties pages to configure the selected routing options action. The pages are:

- Routing Options
- Comment
- Namespaces
- Variables

The **Routing Options** page has the following option:

Option	Description
URI	<p>Select this option to set the URI for the outbound message:</p> <p>To create or edit an expression, click <b>&lt;Expression&gt;</b> (or the <i>expression_fragment</i>, if one is already defined) to display the <a href="#">XQuery/XSLT Expression Editor</a>.</p> <p>Enter an expression that returns a URI. This overrides the URI for the invoked service.</p>
QoS	<p>Select this option to set the Quality of Service element:</p> <p>Select a QoS option from the drop-down list. This overrides the default.</p>
Mode	<p>Select this option to set the mode to Request or Request-Response.</p> <p>Select the mode from the drop-down list.</p> <p><b>Note:</b> This is normally already automatically set, based on the interface of the service invoked. However, in some cases like Any Soap or Any XML services, this is not so.</p>
Retry Interval	<p>Select this option to set the retry interval.</p> <p>Specify the number of seconds between retries. This overrides the default configured with the invoked service.</p>
Retry Count	<p>Select this option to set the retry count.</p> <p>Specify the number of retries the system must attempt before discontinuing the action. This overrides the default configured with the invoked service.</p>
Priority	<p>Select this option to set the message priority:</p> <p>To create or edit an expression, click <b>&lt;Expression&gt;</b> (or the <i>expression_fragment</i>, if one is already defined) to display the <a href="#">XQuery/XSLT Expression Editor</a>.</p> <p>Enter an expression that returns a positive integer.</p>

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.


Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Routing Table Action Properties

In a message flow, use a routing table to select different routes based upon the results of a single XQuery expression. A routing table action contains a set of routes wrapped in a switch-style condition table.

This is a terminal action, which means you cannot add another action after this one. However, this action can contain request and response actions.

When you add a routing table action to a message flow in the [Message Flow Editor](#), the routing table action contains a case action with a path to a routing action plus a default case action with a path to a default routing action, as shown below. Click **add condition** to add another condition to the routing table.



## Routing Table Properties

In the Message Flow Editor, click the publish table action itself (the **Publish Table** icon or the bounding box connected to the icon) to display the Publish Tables properties page in the Properties view. Use these properties pages to configure the selected publish table action. The pages are:

- Routing Table
- Comment
- Namespaces
- Variables

The Routing Table properties page has the following option:

Option	Description
Expression	<p>An XQuery expression, which at run time returns the value upon which the routing decision will be made.</p> <p>To create or edit an XQuery expression, click <b>&lt;Expression&gt;</b> (or the <i><b>expression_fragment</b></i>, if one is already defined) to display the <a href="#">XQuery/XSLT Expression Editor</a>.</p>

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Case Action Properties

In the Message Flow Editor, click a case action to display its properties in the Properties view. Use this properties page to configure the selected case action, as described below:

Option	Description
<ul style="list-style-type: none"> <li>Operator</li> <li>Value</li> </ul>	<p>Select a comparison operator from the list. Then enter a value against which the value returned from the XQuery expression defined for the routing table action will be evaluate</p>

## Routing Action Properties

See [“Routing Action Properties” on page 3-79](#).

## Service Callout Action Properties

In a message flow, use a service callout action to configure a synchronous (blocking) callout to an ALSB-registered proxy or business service.

In the [Message Flow Editor](#), click a service callout action to display its properties in the Properties view. Use these properties pages to configure the selected service callout action. The pages are:

- Service Callout
- Comment
- Namespaces
- Variables

The Service Callout page has the following options:

Option	Description
Service	The target service for the service callout action. Click <b>Browse</b> to select a proxy service or business service from a list.
Invoking	The operation to be invoked on the target service. This option appears only if the selected service is WSDL-based and has operations that can be invoked on the service.
Configure Soap Body or Configure Payload Document	Specify how you want to configure the request and response messages by selecting one of the following options: <ul style="list-style-type: none"><li>• Select <b>Configure SOAP Body</b> to configure the SOAP Body. Selecting this option allows you to use <code>\$body</code> directly. This option supports SOAP-RPC encoded, which is not supported when configuring payload parameters or document.</li><li>• Select <b>Configure Payload Parameters</b> or <b>Configure Payload Document</b> to configure the payload.</li></ul>

Subsequent configuration options depend on the kind of service you selected in step 3 and on the kind of configuration options you chose for that service in step 5. [Table 3-1](#) shows the options available for each service type.

Selected Service Type	“Configure SOAP Body” Options	“Configure Payload Parameters” Options or “Configure Payload Document” Options
<ul style="list-style-type: none"> <li>• SOAP RPC</li> </ul>	<ul style="list-style-type: none"> <li>• <a href="#">SOAP Request Body and SOAP Response Body</a></li> <li>• <a href="#">SOAP Request Header and SOAP Response Header</a> (optional)</li> </ul>	<ul style="list-style-type: none"> <li>• <a href="#">Request Parameters and Response Parameters</a></li> <li>• <a href="#">SOAP Request Header and SOAP Response Header</a> (optional)</li> </ul>
<ul style="list-style-type: none"> <li>• SOAP Document</li> <li>• Any SOAP</li> </ul>	<ul style="list-style-type: none"> <li>• <a href="#">SOAP Request Body and SOAP Response Body</a></li> <li>• <a href="#">SOAP Request Header and SOAP Response Header</a> (optional)</li> </ul>	<ul style="list-style-type: none"> <li>• <a href="#">Request Document and Response Document</a></li> <li>• <a href="#">SOAP Request Header and SOAP Response Header</a> (optional)</li> </ul>
<ul style="list-style-type: none"> <li>• XML</li> <li>• Any XML</li> <li>• Messaging</li> </ul>	<ul style="list-style-type: none"> <li>• <a href="#">SOAP Request Body and SOAP Response Body</a></li> </ul>	<ul style="list-style-type: none"> <li>• <a href="#">Request Document and Response Document</a></li> </ul>

The following table provides instructions for each of the options listed in the table above.

---

For These Options...	Follow These Steps...
<b>SOAP Request Body and SOAP Response Body</b>	To configure these options, <ul style="list-style-type: none"><li data-bbox="508 439 1150 522">• In the <b>SOAP Request Body</b> field, enter the name of a variable to hold the XML of the SOAP Body element for the callout request.</li><li data-bbox="508 534 1150 612">• In the <b>SOAP Response Body</b> field, enter the name of a variable to which the XML of the SOAP Body element on the response will be bound.</li></ul>
<b>SOAP Request Header and SOAP Response Header</b>	To configure these options, <ul style="list-style-type: none"><li data-bbox="508 685 1150 769">• In the <b>SOAP Request Header</b> field, enter the name of a variable to hold the XML of the SOAP Header element for the callout request  You must wrap the input document for the SOAP Request Header with <code>&lt;soap-env:Header&gt; . . . &lt;/soap-env:Header&gt;</code>.</li><li data-bbox="508 876 1150 960">• In the <b>SOAP Response Header</b> field, enter the name of a variable to which the XML of the SOAP Headers on the response, if any, will be bound.</li></ul>

---

---

For These Options...	Follow These Steps...
<b>Request Parameters and Response Parameters</b>	<p>To configure options,</p> <ul style="list-style-type: none"><li>• In the <b>Request Parameters</b> fields, enter names for the variables that will be evaluated at run time to provide values for the request parameters.</li></ul> <p>You must provide only the core payload documents in the input variable—the SOAP package is created for you by AquaLogic Service Bus. In other words, do not wrap the input document with <code>&lt;soap-env:Body&gt; . . . &lt;/soap-env:Body&gt;</code>.</p> <p>For example, when creating a body input variable that is used for this request parameter, you would define that variable's contents using the XPath statement <code>body/*</code> (to remove the wrapper <code>soap-env:Body</code>), not <code>\$body</code> (which results in keeping the <code>soap-env:Body</code> wrapper).</p> <ul style="list-style-type: none"><li>• In the <b>Response Parameters</b> fields, enter the names of the variables to which the responses will be assigned at run time.</li></ul>

---

For These Options...	Follow These Steps...
<b>Request Document and Response Document</b>	<p>To configure these options,</p> <ul style="list-style-type: none"> <li>In the <b>Request Document Variable</b> field, enter the name of a variable to assign a request document to. <p>For <i>SOAP Document-type</i> services, the variable is evaluated at runtime to form the body of the SOAP message sent to the service. For <i>Any XML</i> services, the variable is evaluated at runtime to form the body of the XML message sent to the service.</p> <p>For SOAP Document-type services and for Any XML services, you provide only the core payload documents in the input variable—the SOAP package is created for you by AquaLogic Service Bus. In other words, do not wrap the input document with <code>&lt;soap-env:Body&gt; . . . &lt;/soap-env:Body&gt;</code>.</p> <p>For example, when creating a body input variable that is used for this request parameter, you would define that variable's contents using the XPath statement <code>body/*</code> (to remove the wrapper <code>soap-env:Body</code>), not <code>\$body</code> (which results in keeping the <code>soap-env:Body</code> wrapper).</p> <p>For <i>Messaging</i> services, the variable is evaluated to form the body of the message, based on the type of data expected by the service. The following restrictions apply to variables used with Messaging services:</p> <ul style="list-style-type: none"> <li>For services that expect binary data, the variables must have a <code>ctx:binary-content</code> element.</li> <li>For services that expect MFL data, the variable must have the XML equivalent.</li> <li>For services that expect text data, the variable is a string.</li> </ul> </li> <li>In the <b>Response Document Variable</b> field, enter the name of the variable to which a response document will be assigned at run time.</li> </ul>

Optionally, add one or more transport header actions. For more information about transport header actions, see [“Transport Headers Action Properties” on page 3-90](#)

**Note:** In addition to the transport headers you specify, headers are added by the ALSB binding layer.

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Skip Action Properties

In a message flow, use the skip action to specify that at run time, the execution of the current stage is skipped and the processing proceeds to the next stage in the message flow. This action has no parameters and can be used in the request, response or error pipelines.

In the [Message Flow Editor](#), click a skip action to display its properties in the Properties view. Use these properties pages to configure the selected skip action. The pages are:

- Comment
- Namespaces
- Variables

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Stage Node Properties

In a message flow, use a stage node as a container for actions in a message flow. You can string multiple stages together, to compartmentalize processing logic.

In the [Message Flow Editor](#), click a stage node to display its properties in the Properties view. Use these properties pages to configure the selected stage node. The pages are:

- Stage
- Namespaces
- Variables

The Stage page has the following options:

Option	Description
Name	Enter a name for the stage node.
Description	Enter a description of the stage node.

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Transport Headers Action Properties

In a message flow, use a transport header action to set header values in messages.

In the [Message Flow Editor](#), click a transport headers action to display its properties in the Properties view. Use these properties pages to configure the selected transport headers action. The pages are:

- Transport Headers
- Comment
- Namespaces
- Variables

The Transport Header page has the following options:

Option	Description
Direction	<p>4. From the <b>Set Transport Headers for</b> list, select one of the following, to specify to the run time which of the message context locations are to be modified:</p> <ul style="list-style-type: none"> <li>– <b>Outbound Request</b> - Select this option to set header values for outbound requests (the messages sent out by a proxy service in route, publish, or service callout actions). This header element is located in the message context as follows:           <pre data-bbox="602 626 1224 678">\$outbound/ctx:transport/ctx:request/tp:headers</pre> </li> <li>– <b>Inbound Response</b> - Select this option to set header values for inbound responses (the response messages a proxy service sends back to clients). This header element is located in the message context as follows:           <pre data-bbox="602 826 1224 874">\$inbound/ctx:transport/ctx:response/tp:headers</pre> </li> </ul>
Pass All Headers	<p>Select this option to pass all headers through from the inbound message to the outbound message or vice versa. Every header in the source set of headers will be copied to the target header set, overwriting any existing values in the target header set.</p>
Headers	<p>Click <b>Add Header</b> to add a header to the <b>Headers</b> table. Then configure each header as described in the following rows.</p> <p>You can add as many headers as necessary to this table. You do not have to order the headers in the table, because the run time declares namespaces and places header elements in their proper order when generating the corresponding XML.</p>

---

Option	Description
Headers: Name:	<p data-bbox="462 357 938 383">Specify a header by doing either of the following:</p> <ul data-bbox="462 395 1162 604" style="list-style-type: none"><li data-bbox="462 395 1162 508">• From the drop-down list in the <b>Name</b> column, select a header name. The list contains all of the predefined header names for the target transport (for example, <b>Content-Type</b> for HTTP transports, <b>JMSCorrelationID</b> for JMS transports, etc.).</li><li data-bbox="462 520 1162 604">• Enter a header name in the <b>Other</b> field. If that header name is not one of the predefined headers for this service's transport, it becomes a user-header, as defined by the transport specification.</li></ul>

---

Option	Description
Headers: Action	<p>Select one of the options in this column to specify how to set the header's value:</p> <ul style="list-style-type: none"> <li data-bbox="525 423 823 449">• <b>Set Header to Expression</b>            Selecting this option allows you to use an XQuery or XSLT expression to set the value of the header. The expression can be simple (for example, "text/xml") or a complex XQuery or XSLT expression.            Because the ALSB transport layer defines the XML representation of all headers as string values, the result of any expression is converted to a string before the header value is set. Expressions that return nothing result in the header value being set to the empty string. You cannot delete a header using an expression.  <b>Warning:</b> Not all of the header settings you can specify in this action are honored at run time.</li> <li data-bbox="525 779 709 805">• <b>Delete Header</b>            Specifies that the header is removed from the request or response metadata.  <b>Copy Header from Inbound Request</b> (if you are setting transport headers for the Outbound Request)            or  <b>Copy Header from Outbound Response</b> (if you are setting transport headers for the Inbound Response)            Specifies that this header is copied directly from the corresponding header of the same name from the inbound message to the outbound message and vice versa. For example, if you want to set the SOAPAction header for an outbound request, selecting <b>Copy Header from Inbound Request</b> causes the run time to copy the value from the SOAPAction request header of <code>inbound</code>. In the case of inbound response headers, the source of the header to copy is the response headers of <code>outbound</code>.            If the <b>Copy Header...</b> option is selected for a header that does not exist in the source, this option is ignored and no action is performed on the target for this header.</li> </ul>

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Validate Action Properties

In a message flow, use a validate action to validate elements selected by an XPath expression against an XML schema element or a WSDL resource. You can validate global elements only; ALSB does not support validation against local elements.

In the [Message Flow Editor](#), click a validate action to display its properties in the Properties view. Use these properties pages to configure the selected validate action. The pages are:

- Validate
- Comment
- Namespaces
- Variables

The Validate page has the following options:

Option	Description
XPath	An XPath expression that specifies the elements to be validated. To create or edit the XPath expression, click <XPath> (or the <b>XPath_fragment</b> , if one is already defined) to display the <a href="#">XPath Expression Editor</a> .
In Variable	The name of the variable to hold the element to be validated. Enter the name of the variable, or, if Content Assist is on, press <b>Ctrl-Space</b> to display a list of declared variables.
Against Resource	An XML schema element or a WSDL resource against which the elements selected by the XPath expression (in the <b>XPath</b> field described above) are validated.
Save Variable or Raise Error	To save the result of this validation (a boolean result), select <b>Save Variable</b> and enter the name of the variable in which you want to save the result.  Alternatively, to raise an error if the element fails validation against the WSDL or XML schema element, select <b>Raise Error</b> .

Use the Comment page to add a comment, if desired:

Use the Namespaces page to see a list of defined namespaces or to create a new one.

Use the Variables page to see a list of defined context variables or to create a new one. For more information about context variables, see [Message Context](#) in the *AquaLogic Service Bus User Guide*.

## Modify JAR Dependencies dialog

In ALSB, JAR resources can contain classes that depend on other classes in different JARs. Use the Modify JAR Dependencies page to add or remove referenced JAR resources. Use the **Up** and **Down** buttons to reorder the hierarchy (order of precedence) of referenced JARs. For more information, see [JARs](#) in *Using the AquaLogic Service Bus Console*.

Option	Description
Available JARs	The project name and the name of the folder, if applicable, in which the JAR resources reside. This column shows all available JARs in the current workspace.
JAR references	The name and path of the referenced JAR resources. This column shows all the JARs currently configured as dependencies.

## SMTP Servers

The following editor and wizard are provided for working with SMTP servers:

- [Edit SMTP Server page](#)
- [New SMTP Server Resource wizard](#)

### Edit SMTP Server page

Use this page to view the details of an SMTP server and edit the configuration, if required. For descriptions of the fields, see the [New SMTP Server Resource wizard](#). For more information, see [Editing SMTP Servers](#) in *Using the AquaLogic Service Bus Console*.

## New SMTP Server Resource wizard

Use this page to configure a new SMTP server resource. For more information, see [Adding SMTP Servers](#) in *Using the AquaLogic Service Bus Console*.

Option	Description
Description	Enter a description for this SMTP server resource.
Server URL	Enter the URL that points to the SMTP server. This is a required field.
Port Number	Enter a port number for the SMTP server (the default port is 25). This is a required field.
User Name	If access to the target SMTP server requires a user name and password, enter a user name in the User Name field, and the associated password in the <b>Password</b> and <b>Confirm Password</b> fields.  These fields are optional, and required only if the SMTP server is secured.
Password	Enter the associated password.
Confirm Password	Enter the same password you entered for the <b>Password</b> field.

## UDDI Registry Configuration page

Use this page to configure a UDDI registry resource. This page is displayed in the New UDDI Registry Resource wizard and in the UDDI Configuration editor.

For more information, see [UDDI](#) in *Using the AquaLogic Service Bus Console* and [UDDI](#) in the *AquaLogic Service Bus User Guide*.

Option	Description
Description	Enter a description of the registry.
Inquiry URL	The URL of the Inquiry API endpoint used for locating and importing services. Enter an inquiry URL in the format: <code>http://host:port/APPLICATION_SERVER_CONTEXT/uddi/inquiry</code>

Option	Description
Publish URL	The URL of the Publish API endpoint used for publishing services. Enter a <b>publish URL</b> in the format: <code>http://host:port/APPLICATION_SERVER_CONTEXT/uddi/publishing</code>
Security URL	The URL of the Security API endpoint used for getting an authentication token so that you can publish to the registry. Enter a <b>security URL</b> in the format: <code>http://host:port/APPLICATION_SERVER_CONTEXT/uddi/security</code>
Subscription URL	The URL of the Subscription API endpoint used for subscribing to registry changes, creating a registry subscription, and listening for changes to imported services. Enter a <b>subscription URL</b> in the format: <code>http://host:port/APPLICATION_SERVER_CONTEXT/uddi/subscription</code>  By default, the value for <code>APPLICATION_SERVER_CONTEXT</code> in the installer is <code>registry</code> .
User Name	Enter the user name to log into the registry console.
Password (Confirm Password)	Enter the password to log into the registry console.
Validate	Click <b>Validate</b> to validate that a connection can be made to the configured registry.

## Outline view - AquaLogic Service Bus

This view displays a hierarchical view, or outline, of a structured file that is currently open in the editor area. The contents of this view are editor-specific.

In ALSB, when the proxy service editor is open and the Message Flow Editor is selected, the Outline view displays a hierarchical view of the nodes and actions in the message flow. When the Message Flow Editor is displayed, you can switch between the hierarchical view and a thumbnail view of the service, as described in the table below:

Button	Description
	Click this button to display a hierarchical view of the contents of the current editor.
	Click this button to display a graphical thumbnail view of the contents of the Message Flow Editor. When the entire message flow does not fit in the editor, a blue mask appears in the outline view to show what portion of the flow is visible in the editor. To display a different portion of the flow, you can drag the mask to the portion of the flow you want to display in the editor.

## Resource Management

The following are provided for managing resources:

- [Preferences dialog - AquaLogic Service Bus - Type Associations page](#)
- [References view](#)
- [Select Clone Target dialog](#)
- [Select Clone Target dialog](#)

## Preferences dialog - AquaLogic Service Bus - Type Associations page

Use this page to associate one or more file extensions with an ALSB resource type.

Option	Description
Resource Types	This pane lists all the available types of ALSB resources. Select a type to display its assigned file extension associated with the type.

## References view

Use this page to view resource dependencies. This view shows your current selection whether it is in the Project Explorer or the active editor.

Option	Description
Referenced By	A list of the resources outside of this project, folder, or resource that are dependent on resources inside this project or folder, or this resource.
References	A list of the resources outside of this project, folder, or resource on which resources inside this project or folder, or this resource depends.

## Select Clone Target dialog

Use this dialog to specify where to clone a project, as a new project or as a folder under a different project.

Option	Description
Name	Enter a name for the new (cloned) project.
As project or As folder in location	Select <b>As project</b> to clone the project as another project, that is, as a peer to the other projects. Select <b>As folder in location</b> to convert a project (and its contents) into a folder under a project. When you select this option, you must also select the new location.

## Select a Resource dialog

Use this dialog to select a resource, appropriate to the context, that has been created in or imported into the ALSB plug-in. When you click **Browse** from an editor or a wizard, this dialog displays the available resources that are appropriate for the context. The dialog has different names, depending on the type of resource displayed, for example, **Select a WSDL**, **Select a MFL**, **Select an XML Schema**, etc. In some cases, the dialog displays a hierarchical list of items contained in each resource. For example, the **Select an XML Schema** dialog lists elements and types defined in the schemas. The **Select a WSDL** dialog displays ports and bindings defined in the WSDLs.

In some cases, for example, the **Select a WSDL** dialog, you can click the **Consume** button to open the **Service Consumption** dialog, where you can consume services from the following resource types: AquaLogic Enterprise Repository, file system, UDDI, URI, workspace: consume a service residing in the current workspace.

## New Service Key Provider Resource wizard

Use this page to configure a service key provider resource. For more information, see [Service Key Providers](#) in *Using the AquaLogic Service Bus Console*.

Option	Description
Description	Enter a description for the service key provider.
Encryption Key	<ol style="list-style-type: none"> <li>Next to <b>Encryption Key</b>, select the <b>Key</b> check box.</li> <li>Enter a key alias that maps to an X.509 certificate and that supports encryption, or click <b>Browse</b> to display the key aliases from the key store that your realm's PKI credential mapper is using.</li> <li>Enter the password that you use to secure access to the key store. (You set the password when you create the key store.)</li> </ol> <p>When you associate this service key provider with a proxy service, ALSB embeds the X.509 certificate into the proxy service's WSDL. The proxy service then uses this certificate to encrypt the messages that it sends to its endpoint. The proxy service uses the private key in the PKI credential to decrypt the messages that the endpoint returns.</p>
Digital Signature Key	<ol style="list-style-type: none"> <li>Next to <b>Digital Signature Key</b>, select the <b>Key</b> check box.</li> <li>Enter a key alias, or click <b>Browse</b> to display the key aliases from the key store that your realm's PKI credential mapper is using.</li> <li>Enter the password that you use to secure access to the key store. (You set the password when you create the key store.)</li> </ol>
SSL Client Authentication Key	<ol style="list-style-type: none"> <li>Next to <b>SSL Client Authentication Key</b>, select the <b>Key</b> check box.</li> <li>Enter a key alias, or click <b>Browse</b> to display the key aliases from the key store that your realm's PKI credential mapper is using.</li> <li>Enter the password that you use to secure access to the key store. (You set the password when you create the key store.)</li> </ol>

## New WS-Policy wizard

Web Services Policy Framework (WS-policy) is an extensible XML-based framework that extends the configuration of a Web Service with domain specific security assertions and specifies the security requirements, expectations, and capabilities of the Web Service. In ALSB, one of the primary uses of WS-policy is configuring message-level security in proxy services and business

services. For more information, see [Custom WS-Policies](#) in *Using the AquaLogic Service Bus Console*.

Use this page to select a name and location for a new WS-policy resource.

Option	Description
Enter or select the parent folder	Enter or select the name of the project or folder in which to locate a new WS-policy resource.
File Name	Enter a name for this WS-policy.

## Service Accounts

The following are provided for working with service accounts:

- [New Service Account Resource wizard](#)
- [Service Account editor - General Configuration page](#)
- [Service Account editor - Static User Configuration page](#)
- [Service Account editor - User Mappings Configuration page](#)

### New Service Account Resource wizard

Use this wizard to create a new service account resource, as described in the following table.

Option	Description
Description	Enter a description for the service account.
Resource Type	<ul style="list-style-type: none"> <li>To create a service account that provides the user names and passwords that it receives from incoming client requests, select <b>Pass Through</b> and click <b>Finish</b>.</li> <li>To create a service account that provides a user name and password that you save with the service account configuration, select <b>Static</b>. Continue as described in <a href="#">Service Account editor - Static User Configuration page</a>.</li> <li>To create a service account that maps the user name from one or more authenticated clients to user names and passwords that you specify, select <b>Mapping</b>. Continue as described in <a href="#">Service Account editor - User Mappings Configuration page</a>.</li> </ul>

For more information, see [Service Accounts](#) in *Using the AquaLogic Service Bus Console*.

## Service Account editor - General Configuration page

Use this page to configure a service account resource, as described in the following table.

Option	Description
Description	Enter a description for the service account.
Resource Type	<p>Leave the resource type as is, or select a different resource type:</p> <ul style="list-style-type: none"> <li>A <b>Pass Through</b> type provides the user names and passwords that it receives from incoming client requests.</li> <li>A <b>Static</b> type provides a user name and password that you save with the service account configuration. Configure this type on the <a href="#">Service Account editor - Static User Configuration page</a>.</li> <li>A <b>Mapping</b> type maps the user name from one or more authenticated clients to user names and passwords that you specify. Configure this type on the <a href="#">Service Account editor - User Mappings Configuration page</a>.</li> </ul>

For more information, see [Service Accounts](#) in *Using the AquaLogic Service Bus Console*.

## Service Account editor - Static User Configuration page

Use this page to save a user name and password with the service account configuration. The service account encodes this user name and password in the outbound request. For more information, see [Service Accounts](#) in *Using the AquaLogic Service Bus Console*.

Option	Description
User Name	Enter a user name for this service account.
Password	Enter the associated password.
Confirm Password	Enter the same password you entered for the <b>Password</b> field.

## Service Account editor - User Mappings Configuration page

Use this page to create a service account that maps the user name from one or more clients to user names and passwords that you specify. For more information, see [Service Accounts](#) in *Using the AquaLogic Service Bus Console*.

Option	Description
Remote Users	In the <b>Remote User Name</b> and <b>Remote Password</b> fields, enter the user name and password that you want to send in outbound requests.  (Optional) Add additional remote users in the Remote Users table.

Option	Description
Local User Mappings	<p>To map <i>authorized</i> clients to remote user names and passwords, in the <b>Local User Name</b> field, enter the name that identifies a client that has been authenticated on its inbound request.</p> <p>If you have not already added this user in the Security Configuration module of the ALSB Console, do so before you use this mapping in a runtime environment. See <a href="#">Adding Users</a> in <i>Using the AquaLogic Service Bus Console</i>. ALSB lets you create a mapping for a non-existent local user, but the mapping will never match an authenticated user and will never be used.</p> <p>From the <b>Remote User Name</b> list, select the user name that you want to send in outbound requests for the authenticated user you specified in the <b>Local User Name</b> field.</p>
Map Anonymous Requests	<p>To map <i>anonymous</i> clients to remote user names, select the <b>Map Anonymous Requests</b> check box.</p> <p>From the <b>Select Remote User</b> list, select the user name that you want to send in outbound requests for all anonymous users.</p>

## Expression Editors

The following editors help you to write expressions for use in services.

- [XQuery/XSLT Expression Editor](#)
- [XPath Expression Editor](#)
- [Condition Editor](#)

### XQuery/XSLT Expression Editor

Use the XQuery/XSLT Expression editor to create variable structures, define user namespaces, use predefined message context variables to build inline XQuery expressions, build inline XQuery expressions manually, and select XQuery or XSLT resources for execution as inline XQueries.

For more information about using XQueries, see [Working with Variable Structures](#) in the *AquaLogic Service Bus User Guide*

The XQuery/XSLT Expression editor contains two panels, each containing three tabs.

Use the panel on the left to write or construct the expression. The panel contains these pages (tabs):

- [Expression page](#)
- [XQuery Resource page](#)
- [XSLT Resource page](#)

Use the tabs in the panel on the right to manage the variables, namespaces, and XQuery functions you can use to construct an XQuery or XSLT. The panel contains these pages (tabs):

- [Variable Structures page](#)
- [Namespace Definitions page](#)
- [XQuery Functions page](#)

## XPath Expression Editor

Use the XPath Expression Editor to create an XPath expression, which is then inserted into the location from which you launched the editor.

The XPath Expression Editor contains these pages:

- [Expression page](#)
- [Variable Structures page](#)
- [Namespace Definitions page](#)
- [XQuery Functions page](#)

You can write an expression directly in the **Expression** text field, or you can drag variables from the Variable Structure page and drag XQuery functions from the XQuery Functions page to construct a valid XPath expression.

When you are finished constructing the expression, you can click **Test** to test the expression on a running server. Or click **OK** to insert the expression without testing it.

## Condition Editor

Use the Condition Editor to create an inline XQuery condition.

Use the panel on the left to write or construct the condition. The panel contains these tabs, each of which is described below:

- [Expression page](#)
- [Condition Builder page](#)

Use the tabs in the panel on the right to manage the variables, namespaces, and XQuery functions you can use to construct a condition. The panel contains the following tabs. They are the same as the tabs in the right-hand panel of the XQuery/XSLT Expression Editor, and the following links display the help for those tabs in the XQuery/XSLT Expression Editor.

- [Variable Structures page](#)
- [Namespace Definitions page](#)
- [XQuery Functions page](#)

## Condition Builder page

Use the Condition Builder page to build an inline condition. This page appears only in the [Condition Editor](#).

Build an expression in the Condition Builder as follows:

1. Select **Comparison Expression** to build a comparison expression or select **Unary Expression** to build a unary expression.
2. If you chose **Comparison Expression**, do the following:
  - a. In the **Operand** field, enter the name of the operand you want to compare to a value. Alternatively, drag an item from the **Variable Structures** tab on the right to the **Operand** field.
  - b. In the **Value** field, enter the value against which to compare the operand. Alternatively, drag item from the **Variable Structures** tab on the right to the **Value** field.
  - c. Select a comparison operator from the **Operator** list.
  - d. Go to step 4.
3. If you chose **Unary Expression**, do the following:
  - a. Select or deselect the **Not** check box to indicate whether to evaluate the expression as true or not true, that is, to specify whether the expression should be enclosed by not().
  - b. Enter an expression in the text field, or construct it by dragging items from the **Variable Structures** tab on the right.

4. Do either of the following:
  - Click **Add** to add a new statement to the expression in the **Condition Expression** field.
  - Select a statement in the **Condition Expression** field, then click **Update** to modify the statement.
5. Click **Test** to test the expression in a running server, or click **OK** to insert the condition in the message flow.

## Expression page

This page appears on the [XQuery/XSLT Expression Editor](#), the [XPath Expression Editor](#), and the [Condition Editor](#).

The Expression page contains a text field where you can build expressions by typing directly into the field or by dragging items from the [Variable Structures page](#) or the [XQuery Functions page](#) on the right side of the editor.

Click **Test** to test the expression in an ALSB domain on a running server. WebLogic Server is packaged with ALSB, so an installation of ALSB includes an embedded server you can use for testing purposes.

## XQuery Resource page

This page appears in the [XQuery/XSLT Expression Editor](#) only.

In the message flow of a proxy service, you can assign XQuery expressions to message context variables, assign if-then-else actions based on the Boolean result of an XQuery expression, insert the result of an XQuery expression at an identified place relative to an XPath expression, specify the message context that you want to log through XQuery expressions on context variables, and so on.

Use the XQuery Resource page to configure an XQuery transformation to be executed in the message flow of a proxy service.

Field	Description
XQuery	The XQuery resource to be executed. Click <b>Browse</b> to find and open an XQuery resource that has been registered in ALSB.
Bind Variables	When you select a resource, each input parameter of the transformation is displayed. Each label corresponds to the name of a parameter, and each text box is for defining an XQuery expression to be mapped to the parameter. You must define a mapping for each parameter. Enter the expression directly, or drag variables and structures from the right panel.

## XSLT Resource page

This page appears in the [XQuery/XSLT Expression Editor](#) only.

Use the **XSLT Resource** tab to configure an XSLT transformation to be executed in the message flow of a proxy service.

Field	Description
XSLT	The XSLT resource to execute. Click <b>Browse</b> to find and open a resource registered with ALSB.

Field	Description
Input Document	An XQuery expression for the input document to the transformation, for example <code>\$body</code> .
Bind Variables	<p>A label and a corresponding text box is displayed for each input parameter of the transformation. Each label corresponds to the name of a parameter, and each text box is for defining an XQuery expression to be bound to the parameter. You must define a binding for each parameter. For example, if an XSL transformation has two input parameters named <b>one</b> and <b>two</b>, the <b>Variable Name</b> field has two labels <b>one</b> and <b>two</b>— with a text box associated with each into which the XQuery expression is entered.</p> <p>Enter the expression directly, or drag variables and structures from the right panel.</p> <p>The following XQuery expressions are examples of valid input to this field:</p> <pre>\$body/*[1]</pre> <pre>\$body/po:PurchaseOrder</pre> <p><b>Note:</b> The following variable name is not a valid entry for this field and results in an exception:</p> <pre>body</pre>

## Variable Structures page

This page appears in the [XQuery/XSLT Expression Editor](#), the [XPath Expression Editor](#), and the [Condition Editor](#).

The Variable Structures page displays variables and their contents as trees. It includes the built-in message context variables `attachments`, `body`, `header`, `outbound`, and `inbound`, as well as any user-defined variables. It includes `fault` if the context of the expression is appropriate (that is, in an error handler). The `outbound` variable is always listed; even though it is not valid in every context. If `outbound` is used in invalid contexts, it will be reported when validating.

Each variable structure mapping entry has a label and maps a variable or variable path to one or more structures. The scope of these mappings is a stage or a route node.

You can drag items from this page to the editor's [Expression page](#) to insert them into the current expression. They are inserted as XPath expressions.

To define a new variable and add it to the variable structure tree, click **Add** to open the [Add Variable Structure dialog](#).

For more information about working with variable structures, see [Working with Variable Structures](#) in the *AquaLogic Service Bus User Guide*

## Namespace Definitions page

This page appears in the [XQuery/XSLT Expression Editor](#), the [XPath Expression Editor](#), and the [Condition Editor](#).

The Namespace Definitions page lists default ALSB namespaces, variable namespaces, and user-defined namespaces. Click **Add** to define a new namespace, which is then added to the list of user-defined namespaces. To modify a user-defined namespace, select it in the list, then click **Edit**.

## XQuery Functions page

This page appears in the [XQuery/XSLT Expression Editor](#), the [XPath Expression Editor](#), and the [Condition Editor](#).

The XQuery Functions page lists a set of standard XQuery functions, organized alphabetically and by type. You can drag functions from this page to the editor's [Expression page](#) to insert them into the current expression. When you insert a function into an expression, placeholders are used for parameter values you must supply.

## Add Variable Structure dialog

Use this dialog to define a variable and add it to the tree of variable structures in the [Variable Structures page](#) of the [Expression Editors](#).

You create variable structures in this dialog to define the structure of a variable for design purposes. For example, it is easier to browse the XPath variable in the structure view rather than viewing the XML schema of the XPath variable. Variable structures do not create variables. Variables are created at runtime as the target of the assign action in the stage.

You can declare your own variable structures based on:

- XML types, including
  - Schema elements
  - WSDL elements
  - Schema types
  - WSDL types

- MFLs
- Service interfaces
- Simple types (string or any XML)

You can use this feature directly for all user-defined variables, as well as `$inbound`, `$outbound`, and `$fault`. However, you cannot use it directly to access XML attachments in `$attachments`, headers in `$header`, or documents and RPC parameters in `$body`, with one exception— you can use it directly to access documents and parameters in `$body` for request messages received by a WSDL proxy service.

When you create a variable structure based on XML types, MFLs, or service interfaces, you must enter the following information into the fields at the top of the page:

Option	Description
Structure Label	A display name for the variable you want to create. This display name enables you to give a meaningful name to the structure so you can recognize it at design time but it has no impact at run time.
Structure Path	The path of the variable structure at run time

For more information about working with variable structures, see [Working with Variable Structures](#) in the *AquaLogic Service Bus User Guide*

## New XSL Transformation wizard

Transformation maps describe the mapping between two data types. eXtensible Stylesheet Language Transformation (XSLT) maps describe XML-to-XML mappings. For more information, see [XSL Transformations](#) in *Using the AquaLogic Service Bus Console*.

Use this page to select a name and location for a new XSL transformation. This wizard creates a skeleton for the XSLT. Add details in the XSLT editor.

Option	Description
Enter or select the parent folder	Enter or select the name of the project or folder in which to locate a new XSL transformation.
File Name	Enter a name for this new XSL transformation.

## Split-Join User Interface Reference

The following sections describe the fields and user interface components involved with creating and configuring Split-Joins in ALSB.

- [Split-Join Design Palette](#)
- [Split-Join Properties View - Error Handler](#)
- [Split-Join Properties View - External Services](#)
- [Split-Join Properties View - Assign](#)
- [Split-Join Properties View - Global Properties](#)
- [Split-Join Properties View - For Each](#)
- [Split-Join Properties View - If Activity](#)
- [Split-Join Process Properties View - If and Else If](#)
- [Split-Join Properties View - Invoke External Service](#)
- [Split-Join Properties View - Parallel](#)
- [Split-Join Properties View - Raise Error Page](#)
- [Split-Join Properties View - Receive Page](#)
- [Split-Join Properties View - Reply Page](#)
- [Split-Join Properties View - Scope](#)
- [Split-Join Properties View - Start Node](#)
- [Assign Operation Dialog](#)
- [Copy Literal/XPath 1.0 Expression Dialog](#)
- [Counter Variable Dialog](#)
- [Create/Edit Variable Dialog](#)
- [Create Message Variable Dialog](#)
- [Delete Action Dialog](#)
- [Insert Action Dialog](#)

- [Replace Action Dialog](#)
- [Split-Join Wizard - New Split-Join](#)
- [Split-Join Wizard - Specify Operations](#)
- [Service Browser](#)
- [SOAP Fault Variable Dialog](#)
- [WSDL Browser](#)

## Split-Join Design Palette

The Split-Join Design Palette lists all the controls you can use to construct a Split-Join. To insert a control into a Split-Join, drag the icon from the palette to the Split-Join editor. When you drag an item to the editor, one or more circles (drag-points) appear (  ) to indicate that you can drop the dragged item in that position on the editor. When you drag the item into such a circle, it is highlighted (  ) to show that you can drop the item there.

## Controls

The Split-Join Design palette is organized into the following categories:

- Communication
- Flow Control
- Message Processing

The following table describes the controls you can add to a Split-Join:

Control	Description
<b>Communication</b>	
Invoke Service	Invoke Service invokes a WSDL-based, non-transport-typed Business Service or a WSDL-based Proxy Service. For configuration properties, see <a href="#">Split-Join Properties View - Invoke External Service</a> .

<b>Control</b>	<b>Description</b>
Reply	Reply sends a response or fault back to the ALSB Message Flow. For configuration properties, see <a href="#">Split-Join Properties View - Reply Page</a> .
<b>Flow Control</b>	
Parallel	Parallel creates a fixed number of configured parallel branches. For configuration properties, see <a href="#">Split-Join Properties View - Parallel</a> .
For Each	For Each executes logic configured within its Scope a specified number of times. For configuration properties, see <a href="#">Split-Join Properties View - For Each</a> .
If	If provides conditional behavior within a Split-Join. For configuration properties, see <a href="#">Split-Join Properties View - If Activity</a> .
Raise Error	Raise Error generates an error that causes the Split-Join to stop normal processing. If the error is not handled using an Error Handler, the Split-Join will terminate and a Fault will be sent to the ALSB Message Flow. For configuration properties, see <a href="#">Split-Join Properties View - Raise Error Page</a> .
<b>Message Processing</b>	
Assign	Use Assign for data manipulation, including initializing and updating a Variable. For configuration properties, see <a href="#">Split-Join Properties View - Assign</a> .

## Split-Join Properties View - Error Handler

Use this properties page to review and configure the selected Error Handler in a Split-Join.

The Error Handler receives and handles all of the errors that are raised in a Split-Join.

The catchAll tab has the following options.

Option	Description
SOAP Fault Variable Name	Defines a variable to contain SOAP (1.1 or 1.2) faults. If the Error Handler is executed due to a SOAP fault received from invoked external services, this variable is populated with the received SOAP fault.

## Split-Join Properties View - External Services

Use this properties page to review and configure the selected External Services (business and proxy services) invoked from the Split-Join.

Use External Services to call Services outside of the context of the Split-Join.

When you select External Service, a dashed blue line appears pointing to the Invoke Service associated with the service.

Option	Description
Service Location	Shows the location of the External Service within the ALSB Configuration. The location path is a link that opens the service file.

## Split-Join Properties View - Assign

Use this properties page to review and configure the selected Assign in an Split-Join.

Use Assign for data manipulation, including initializing and updating a Variable.

This page has two tabs:

- Assign
- General

The Assign tab has the following options:

Option	Description
Add	<p>Provides the following options for adding operations to the Assign:</p> <ul style="list-style-type: none"> <li>• Assign launches the <a href="#">Assign Operation Dialog</a></li> <li>• Copy launches the <a href="#">Copy Literal/XPath 1.0 Expression Dialog</a></li> <li>• Delete launches the <a href="#">Delete Action Dialog</a></li> <li>• Insert launches the <a href="#">Insert Action Dialog</a></li> <li>• Replace launches the <a href="#">Replace Action Dialog</a></li> </ul>
Edit	<p>Launches the appropriate dialog for the selected item (as listed for Add, above)</p>
Delete	<p>Deletes the currently selected operation(s)</p>

Option	Description
Up and Down Arrows	Click the up arrow or down arrow to change the position of the currently selected operation. This option is only enabled when more than one operation exists.
Assign Operations	<ul style="list-style-type: none"> <li> <b>Assign</b> the result of an XQuery expression to a Variable.            To create an Assign operation, select <b>Assign</b> from the Add Button to launch the <a href="#">Assign Operation Dialog</a>.         </li> <li> <b>Copy</b> the information specified by an XPath expression from a source document to a destination document.            To create a Copy operation, select <b>Copy</b> from the Add Button to launch the <a href="#">Copy Literal/XPath 1.0 Expression Dialog</a>.         </li> <li> <b>Delete</b> a set of nodes specified by an XPath Expression.            To create a Delete operation, select <b>Delete</b> from the Add Button to launch the <a href="#">Delete Action Dialog</a>.         </li> <li> <b>Insert</b> the result of an XQuery expression at an identified place relative to nodes selected by an XPath Expression.            To create an Insert operation, select <b>Insert</b> from the Add Button to launch the <a href="#">Insert Action Dialog</a>.         </li> <li> <b>Replace</b> a node or the contents of a node specified by an XPath Expression.            To create a Replace operation, select <b>Replace</b> from the Add Button to launch the <a href="#">Replace Action Dialog</a>.         </li> </ul>

The General tab has the following options:

Option	Description
Label	Enter a label for the file defining the External Service.
Documentation	Enter a description and/or comments.

## Split-Join Properties View - Global Properties

Use this properties page to review and configure the Global Properties of the selected Split-Join.

The initial node in a Split-Join specifies its Global Properties. Among these properties, Global Variables and associated External Services can be reviewed and configured by expanding the left-side arrow. The global Error Handler can be reviewed and configured by expanding the right-side arrow.

This page has two tabs:

- Imports
- General

The Imports tab has the following options:

Option	Description
WSDL Imports	Displays WSDL Imports used by the Split-Join. Select a WSDL in the list and right-click to delete it.
Schema Imports	Displays Schema Imports used by the Split-Join. Select a Schema in the list and right-click to delete it.

The General tab has the following options:

Option	Description
Label	Enter a label for the file defining the Process Node.
Documentation	Enter a description and/or comments.

## Split-Join Properties View - For Each

Use this properties page to review and configure the selected For Each in a Split-Join.

For Each executes logic configured within its Scope a specified number of times.

This page has two tabs:

- For Each

- General

The For Each tab has the following options:

Option	Description
Parallel	Select one of the following options: <ul style="list-style-type: none"> <li>• If <b>yes</b> is selected, each iteration of For Each is executed in parallel.</li> <li>• If <b>no</b>, each iteration of For Each is executed sequentially.</li> </ul>
Counter Variable Name	Defines an implicit variable within the Scope of the For Each. Each iteration of the For Each contains an isolated instance of this variable. In turn, every instance is set to an iteration number; for example, the first iteration has its value set to <b>Start Counter Value</b> , the second iteration to <b>Start Counter Value+1</b> , etc.
Start Counter Value	The value of the Counter Variable for the first iteration of For Each. Determined as the result of an XPath 1.0 expression. The result must be “1” or more. (“0” is not a valid Start Counter Value.)  The browse button launches the <a href="#">Copy Literal/XPath 1.0 Expression Dialog</a> . The built Expression should generate an integer for the initial Start Count Value.
Final Counter Value	The value of the Counter Variable for the final iteration of For Each. Determined as the result of an XPath 1.0 expression. The result must be “1” or more. (“0” is not a valid Start Counter Value.)  The browse button launches the <a href="#">Copy Literal/XPath 1.0 Expression Dialog</a> . The built expression should generate an integer for the Final Count Value.

The **General** tab has the following options:

Option	Description
Label	Enter a label for the file defining the For Each condition.
Documentation	Enter a description and/or comments.

## Split-Join Properties View - If Activity

Use this properties page to review and configure the selected If in a Split-Join.

Use If to provide conditional behavior within an Split-Join.

Option	Description
Label	Enter a label for the file defining the If Condition.
Documentation	Enter a description and/or comments.

## Split-Join Process Properties View - If and Else If

Use this properties page to review and configure the selected If or Else If in an Split-Join.

The If and Else If controls provide conditional behavior within an Split-Join.

Option	Description
Condition	Define an XPath 1.0 expression that evaluates to true or false. If the condition evaluates to true, the associated If/Else If branch is executed.  Click the browse button to launch the <a href="#">Copy Literal/XPath 1.0 Expression Dialog</a> .

## Split-Join Properties View - Invoke External Service

Use this properties page to review and configure the selected Invoke External Service in a Split-Join.

Use Invoke External Service to invoke a WSDL-based, non-transport-typed Business Service or a WSDL-based Proxy Service.

This page has four tabs:

- Operation
- Input Variable
- Output Variable
- General

The Operation tab has the following options:

Option	Description
Operation	The operation to be invoked by the Service Browse to select an operation from the <a href="#">Service Browser</a> .
Service Location	The location of the invoked Service. Click the location path to open the service file.

The Input Variable tab has the following options:

Option	Description
Message Variable	A list of message type variables with the type matching the operation's input message type. Select <b>Create New Variable</b> to define a new message variable.  <b>Note:</b> If message type variables with the type matching the operation's input message type do not exist, you <i>must</i> define a new message type variable with the required type.
Message Type Namespace	The namespace of the operation's input message type.
Message Type	The operation's input message type.

The Output Variable tab has the following options:

Option	Description
Message Variable	A list of message type variables with the type matching the operation's output message type.  <b>Note:</b> If message type variables with the type matching the operation's output message type do not exist, you <i>must</i> define a new message type variable with the required type.
Message Type Namespace	The namespace of the operation's output message type.
Message Type	The operation's output message type.

The General tab has the following options:

Option	Description
Label	Enter a label for the file defining the Invoke Service
Documentation	Enter a description and/or comments

## Split-Join Properties View - Parallel

Use this properties page to review and configure the selected Parallel in a Split-Join.

Parallel creates a fixed number of configured parallel branches.

Option	Description
Label	Enter a label for the file defining the Parallel.
Documentation	Enter a description and/or comments.

## Split-Join Properties View - Raise Error Page

Use this properties page to review and configure the selected Raise Error in an Split-Join.

Raise Error establishes an error condition under which the execution of the process will halt.

Option	Description
Label	Enter a label for the file defining the Raise Error.
Documentation	Enter a description and/or comments.

## Split-Join Properties View - Receive Page

Use this properties page to review and configure the selected Receive in a Split-Join.

This page has three tabs:

- Operation
- Variable

- General

The Operation tab has the following options:

Option	Description
Operation	The operation to be invoked by the Receive. Browse to select an operation from the <a href="#">WSDL Browser</a> .

The Variable tab has the following options:

Option	Description
Message Variable	A list of the message variables whose type matches the operation's output message type Select <b>Create New Variable</b> to define a new message variable. <b>Note:</b> If message type variables with the type matching the operation's output message-type do not exist, you <i>must</i> define a new message type variable with the required type.
Message Type Namespace	The namespace of the operation's output message type.
Message Type	The operation's output message type.

The General tab has the following options:

Option	Description
Label	Enter a label for the file defining the Reply
Documentation	Enter a description and/or comments

## Split-Join Properties View - Reply Page

Use this properties page to review and configure the selected Reply in a Split-Join.

Reply sends a response or fault back to the ALSB message flow.

This page has three tabs:

- Operation
- Variable
- General

The Operation tab has the following options:

Option	Description
Operation	The operation to be invoked by the Reply.
Binding	
WSDL Ref	

The Variable tab has the following Select options:

Option	Description
Message Variable	<p>A list of the message variables whose type matches the operation's output message type.</p> <p>Select <b>Create New Variable</b> to define a new message variable.</p> <p><b>Note:</b> If message type variables with the type matching the operation's output message-type do not exist, you <i>must</i> define a new message type variable with the required type.</p>
Message Type Namespace	The namespace of the operation's output message type.
Message Type	The operation's output message type.
<b>Fault Options</b>	
Pick WSDL Fault/SOAP Fault	Determine whether the fault reply is a fault message defined in the operation of the WSDL or an explicit SOAP fault message.
Fault Name	Select a fault name from the list of faults defined in the operation of the WSDL.

Option	Description
Message Variable	<p>A list of the Message Variables whose type matches the operation's output message type.</p> <p>Select <b>Create New Variable</b> to define a new message variable.</p> <p><b>Note:</b> If message type variables with the type matching the operation's output message-type do not exist, you <i>must</i> define a new message type variable with the required type.</p>
Message Type Namespace	The namespace of the operation's output message type.
Message Type	The operation's output message type.
SOAP Fault	<p>Select SOAP Fault</p> <p>See <a href="#">SOAP Fault Variable Dialog</a>.</p>
Propagate SOAP Fault	<p>Propagate the SOAP fault in the SOAP fault variable defined in the Error Handler.</p> <p>See <a href="#">Split-Join Properties View - Error Handler</a>.</p>

The **General** tab has the following options:

Option	Description
Label	Enter a label for the file defining the Reply
Documentation	Enter a description and/or comments

## Split-Join Properties View - Scope

Use this properties page to review and configure the selected Scope in a Split-Join.

The Scope creates a context which influences the behavior of its enclosed controls. Local variables and the Error Handler defined within the Scope are restricted to this context.

Option	Description
Label	Enter a label for the file defining the Scope.
Documentation	Enter a description and/or comments.

## Split-Join Properties View - Start Node

Use this properties page to review and configure the Start Node in a Split-Join.

The Start Node contains global variables and imports introspected from the WSDL Operation. It can also have an associated global Error Handler.

This page has two tabs:

- Imports
- General

The **Imports** tab has the following options:

Option	Description
WSDL Imports	WSDLs imported by the Split-Join
Schema Imports	Schemas imported by the Split-Join

The **General** tab has the following options:

Option	Description
Label	Enter a label for the file defining the Scope.
Documentation	Enter a description and/or comments.

## Split-Join Properties View - Variable

Use this properties page to review and configure Variables in the selected Split-Join.

Option	Description
(tree)	Depicts the hierarchical structure of the Variable's type.
Edit	Click to display the <a href="#">Create/Edit Variable Dialog</a> , where you can modify the Variable's name and type.

## Assign Operation Dialog

Use this dialog to create an Assign Operation for use in an Assign.

Option	Description
Expression	An XQuery expression used to create the data that will be assigned to the Variable.  Clicking the expression launches the XQuery editor.
Variable	A variable to which the result of the XQuery expression is assigned.  Only previously defined Variables, the Counter Variable, and SOAP Fault Variables (for Error Handlers) are available.

## Copy Literal/XPath 1.0 Expression Dialog

Use this dialog to create a Copy Operation for use in an Assign.

Option	Description
Choose Type	Allows the user to select the desired type: Variable, Expression, Literal, or XML Fragment. Literals and XML fragments are available only in the Select From menu.
Choose Type - Variable	Select an XPath on a Variable. Use this option when simple node selection on a Variable is required.  When a node is selected by expanding the Variable tree, and XPath 1.0 expression is automatically generated.

Option	Description
Choose Type - Expression	<p>Create an Xpath 1.0 expression to select a node from a Variable. Use this option when more complex Xpaths (potentially with predicates) are required to select a node on a Variable.</p> <p>Click the browse button to use the Copy Literal/XPath 1.0 Expression dialog.</p> <p><b>Note:</b> The entered Xpath 1.0 expression should only copy to one XML node/element, or there will be runtime errors.</p>
Choose Type - Literal	A Literal string entered by the user
Choose Type - XML Fragment	An XML fragment entered by the user.

## Counter Variable Dialog

Use this dialog to create a Counter Variable.

Option	Description
Counter Variable Name	The name of the Counter Variable

## Create/Edit Variable Dialog

Use this dialog to review and/or configure Variables in the Split-Join.

Option	Description
Name	Enter a unique name for the Variable.
Select Variable Type	<p>Select one of the following Variable Types:</p> <ul style="list-style-type: none"> <li>• Built-in Types</li> <li>• Schema Types</li> <li>• Message Types</li> </ul>
Select Variable Type - Basic Types	When selected, only Basic Type Variables are displayed.

Option	Description
Select Variable Type - Schema Types	When selected, all Schema Types in the current ALSB Configuration are displayed.  If “Show only applicable schema types/elements for this Split-Join” is selected, only Schema Types directly applicable to the current Split-Join are displayed. This is checked by default.
Select Variable Type - Message Types	When selected, only message types are displayed.  If “Show only applicable schema types/elements for this Split-Join” is selected, only Schema Types directly applicable to the current Split-Join are displayed. This is checked by default.
Type	The Variable type.
Namespace	The namespace of the Variable’s type.

## Create Message Variable Dialog

Use this dialog to create a new Variable.

Option	Description
Name	Enter a unique name for the Variable.
Type	One of the following Variable types: WSDL message, XSD element, or XSD type (simple, complex, built-in).
Namespace	The namespace of the Variable’s type.

## Delete Action Dialog

Use this dialog to create a Delete Action for use in an Assign.

Option	Description
XPath	An XPath Expression that selects the nodes to be deleted. Click on the XPath to launch the XPath Editor.
In Variable	Variable on which the XPath expression is executed to select the nodes to be deleted.

## Insert Action Dialog

Use this dialog to create an Insert Action for use in an Assign.

Option	Description
Expression	An XQuery 1.0 expression used to create the data that will be inserted at a specified location in a Variable. Click on the Expression to launch the XQuery editor.
Location	The location used to control where the Insert Action is performed relative to the result of the XPath 1.0 Expression. Options include: <ul style="list-style-type: none"> <li>• <b>Before:</b> Immediately before the element specified by the result of the Xpath 1.0 Expression.</li> <li>• <b>After:</b> Immediately after the element specified by the result of the Xpath 1.0 Expression.</li> <li>• <b>as first child of:</b> The first child element of the element specified by the result of the Xpath 1.0 Expression.</li> <li>• <b>as last child of:</b> The last child element belonging to the element specified by the result of the Xpath 1.0 Expression.</li> </ul>
XPath	An XPath that determines the nodes to be selected. Click on the Xpath to launch the <a href="#">XPath Expression Editor</a> .
Variable	A Variable to be evaluated by the XPath.

## Replace Action Dialog

Use this dialog to create a **Replace Action** for use in an Assign.

Option	Description
XPath	An XPath 1.0 Expression used to specify the data (in the Variable) that will be replaced. Click on the XPath to launch the <a href="#">XPath Expression Editor</a> .
Variable	The Variable that contains the data to be replaced
Expression	An XQuery 1.0 expression used to create the data that replaces the data specified by the XPath in the named Variable. Click on the Expression to launch the XQuery 1.0 editor.
Replace entire node	Specifies that the nodes selected by the XPath 1.0 expression defined above are replaced along with all of its contents.
Replace node contents	Specifies that the node is not replaced. Only the contents are replaced.

## Split-Join Wizard - New Split-Join

Use this page to locate and name the new Split-Join

Option	Description
Enter or select the parent folder	Enter the name of the folder to contain this Split-Join, or select a folder from the list.
File Name	Enter a name for the file defining the Split-Join.

## Split-Join Wizard - Specify Operations

Use this page to select an operation for the new Split-Join.

Option	Description
Select Operation	Select the operation from those available in the tree.
Consume	Click this button to import WSDLs from outside your current ALSB configuration that can subsequently be used to select an operation.

## Service Browser

Use this dialog to browse for and select an operation from a Business or Proxy Service in the depicted tree.

## SOAP Fault Variable Dialog

Use this dialog to create a SOAP fault variable.

Option	Description
SOAP Fault Variable Name	The name of the SOAP fault variable.

## WSDL Browser

Use this dialog to browse for and select an operation from a WSDL in the depicted tree.

# Transport Configuration

When you configure a business service or a proxy service, you must configure the transport used by the service. Each transport is configured on its own configuration page.

## *Protocol-Specific* Transport Configuration Pages

Each transport available for business services and proxy services has its own configuration page. Those built into ALSB are:

- “[DSP Transport Configuration page \(Business Services\)](#)” on page 4-2
- “[EJB Transport Configuration page \(Business Services\)](#)” on page 4-3
- “[E-Mail Transport Configuration page \(Business Services\)](#)” on page 4-4
- “[E-Mail Transport Configuration page \(Proxy Services\)](#)” on page 4-5
- “[File Transport Configuration page \(Business Services\)](#)” on page 4-6
- “[File Transport Configuration page \(Proxy Services\)](#)” on page 4-7
- “[FTP Transport Configuration page \(Business Services\)](#)” on page 4-8
- “[FTP Transport Configuration page \(Proxy Services\)](#)” on page 4-9
- “[HTTP Transport Configuration Page \(Business Services\)](#)” on page 4-11
- “[HTTP Transport Configuration Page \(Proxy Services\)](#)” on page 4-13
- “[JMS Transport Configuration page \(Business Services\)](#)” on page 4-14

- “JMS Transport Configuration page (Proxy Services)” on page 4-17
- “JPD Transport Configuration page (Business Services)” on page 4-20
- “MQ Transport Configuration page (Business Services)” on page 4-22
- “MQ Transport Configuration page (Proxy Services)” on page 4-23
- “SB Transport Configuration page (Business Services)” on page 4-24
- “SB Transport Configuration page (Proxy Services)” on page 4-25
- “SFTP Transport Configuration page (Business Services)” on page 4-26
- “SFTP Transport Configuration page (Proxy Services)” on page 4-27
- “Tuxedo Transport Configuration page (Business Services)” on page 4-29
- “Tuxedo Transport Configuration page (Proxy Services)” on page 4-31
- “WS Transport Configuration page (Business Services)” on page 4-33
- “WS Transport Configuration page (Proxy Services)” on page 4-34

## DSP Transport Configuration page (Business Services)

Use this page to configure transport settings for a business service using the DSP (BEA AquaLogic Data Services Platform) transport protocol. For more information on accessing AquaLogic Data Services Platform from ALSB, see [Accessing Data Services Through AquaLogic Service Bus](#).

Option	To create or edit...
Debug Level	Specify one of the following <ul style="list-style-type: none"><li>• 0 - for no debug information</li><li>• 1 - to output information on the request message</li><li>• 3 - to output information on the request and the response message</li></ul>

Option	To create or edit...
Service Account	<ul style="list-style-type: none"> <li>Click <b>Browse</b> and select a service account from the list displayed. If no service account is specified, an anonymous subject is used.</li> </ul>
Dispatch Policy	<p>Select the instance of WebLogic Server Work Manager that you want to use for the dispatch policy for this endpoint. The default Work Manager is used if no other Work Manager exists.</p> <p>The Work Manager is used to post the reply message for response processing. For information about Work Managers, see <a href="#">Using Work Managers to Optimize Scheduled Work</a> and <a href="#">Create Work Manager</a> in the <i>WebLogic Server Administration Console Online Help</i>.</p>

## EJB Transport Configuration page (Business Services)

Use this page to configure transport settings for a business service using the EJB transport protocol.

Option	To create or edit...
<b>Service Account</b>	<ul style="list-style-type: none"> <li>Click <b>Browse</b> and select a service account from the list displayed. If no service account is specified, an anonymous subject is used.</li> </ul>
<b>Supports Transaction</b>	Select this check box to specify transaction support.
<b>Client Jar</b>	Click <b>Browse</b> and select an EJB client JAR resource from the list displayed.
<b>Converter Jar</b>	Click <b>Browse</b> and select an EJB converter class JAR resource from the list displayed. To learn more about EJB client JAR resources and converter classes, see <a href="#">EJB Transport</a> in the <i>AquaLogic Service Bus User Guide</i> .
<b>Home Interface</b>	Select the required EJBHome interface from the options populated by the JAR. The JNDI name in this URI sample must be associated with the EJBHome interface you select here. If the EJB is not of the required type or an EJBHome interface is not specified in the client-jar, a warning will be displayed.
<b>Remote Interface</b>	This field is automatically populated depending on the configuration of the Home Interface.
<b>Target Namespace</b>	This field is populated by information picked up from the JAR.

Option	To create or edit...
<b>Style</b>	<p>Select <b>Document Wrapped</b> or <b>RPC</b> according to your requirements. If two or more methods of your stateless session EJB have the same number and data type of parameters, and you want the operations to be document-oriented, you must specify that they be document-wrapped.</p> <p>The style is important because when routing or publishing to the EJB, <code>\$body</code> must have content that matches the style. Also when calling out to an EJB, the style affects the parameter contents, especially for document wrapped. Secondly one usage pattern is to define an EJB business service and then create a proxy service with the same WSDL that routes to the EJB. In this case care must be taken on the style of the WSDL because the client tool used to invoke the proxy might have limitations on the style of the WSDL.</p>
<b>Encoding</b>	Select <b>Encoded</b> or <b>Literal</b> .
<b>Methods</b>	Select the required methods (you can select multiple methods). Click + to expand the method and: edit the default parameter values and select a converter if provided (or required).

## E-Mail Transport Configuration page (Business Services)

Use this page to configure transport settings for a business service using the e-mail transport protocol.

Option	To create or edit...
SMTP Server	<p>Select an SMTP server.</p> <p>This is a required field if you do not select a JNDI name in the <b>Mail Session</b> field.</p>
Mail Session	<p>Select the JNDI name of a configured session.</p> <p>This is a required field if you do not enter an SMTP server name in the <b>Mail Server</b> address field.</p>
From Name	Enter a display name for the originating e-mail account for this service.
From Address	Enter the originating e-mail account for this service.
Reply To Name	Enter a display name for the reply to e-mail account.
Reply To Address	Enter an e-mail address to reply to.

Option	To create or edit...
Connection Timeout	Enter the timeout interval, in seconds, before the connection is dropped. If you enter 0, there is no timeout.
Request Encoding	Accept the default ISO-8859-1 as the character set encoding for requests in e-mail transports, or enter a different character set encoding.

## E-Mail Transport Configuration page (Proxy Services)

Use this page to configure transport settings for a proxy service using the e-mail transport protocol.

Option	To create or edit...
Service Account	Enter a service account name, or click <b>Browse</b> to select service accounts from a browser.
Managed Server	Select the Managed Server for polling in a clustered domain. This field is available <i>only</i> in a clustered domain.
Polling Interval	Enter a polling interval, in seconds.
E-Mail Protocol	Select POP3 or IMAP as the server type for the e-mail account.
Read Limit	Specify the maximum number of messages to read per polling sweep. Enter 0 to specify no limit.
Pass By Reference	Select this check box to stage the file in the archive directory and pass it as a reference in the headers.  By default when you create a new service, the <b>Pass By Reference</b> option is selected and you must specify the archive directory location.
Pass Attachments by Reference	Select this check box to stage the attachments in the archive directory and pass them as a reference in the headers.  By default, when the <b>Pass By Reference</b> option is selected, the <b>Pass Attachments By Reference</b> option is implicitly true and you must specify the archive directory location.

Option	To create or edit...
Post Read Action	Select what happens to a message after it has been read: <ul style="list-style-type: none"> <li>• <b>Archive</b> - The message is archived.</li> <li>• <b>Delete</b> - The message is deleted.</li> <li>• <b>Move</b> - The message is moved. Move is only available with the IMAP protocol.</li> </ul>
Attachments	Select how attachments are handled: <ul style="list-style-type: none"> <li>• <b>Archive</b> - Attachments are saved to the archive directory.</li> <li>• <b>Ignore</b> - Attachments are ignored.</li> </ul>
IMAP Move Folder	Enter the folder to which the message is moved if the <b>Post Read Action</b> field is set to <b>Move</b> .
Download Directory	Enter a temporary location for downloading e-mails.
Archive Directory	Specify the path to the archive location if the <b>Post Read Action</b> field is set to <b>Archive</b> .  This field is required if the <b>Pass By Reference</b> or <b>Pass Attachments By Reference</b> option is selected.
Error Directory	Enter the file system directory path to write the message and any attachments if there is a problem.
Request Encoding	Accept the default ISO-8859-1 as the character set encoding for requests in E-mail transports, or enter a different character set encoding.

## File Transport Configuration page (Business Services)

Use this page to configure transport settings for a business service using the file transport protocol.

Option	To create or edit...
Prefix	Enter a prefix to be prepended to the file name.  Do not enter * in this field. This character causes a run-time exception.

Option	To create or edit...
Suffix	Enter a suffix to be appended to the file name. This is a required field. Do not enter * in this field. This character causes a run-time exception.
Request Encoding	Accept the default utf-8 as the character set encoding for requests in File transports, or enter a different character set encoding.

## File Transport Configuration page (Proxy Services)

Use this page to configure transport settings for a proxy service using the file transport protocol.

Option	To create or edit...
File Mask	Enter the regular expression for the files to be picked. The default is *.*.
Managed Server	Select the Managed Server for polling in a clustered domain. This field is available <i>only</i> in a clustered domain.
Polling Interval	Enter a polling interval, in seconds. The default is 60.
Read Limit	Specify the maximum number of messages to read per polling sweep. Enter 0 to specify no limit. The default is 10.
Sort By Arrival	Select this check box to specify that events are delivered in the order of arrival. Note that when this option is selected for a proxy service that is executed in a clustered environment, messages are always sent to the same server. In other words, load balancing across servers is ignored when this option is selected.
Scan Subdirectories	Select this check box to recursively scan all the directories.
Pass By Reference	Select this check box to stage the file in the archive directory and pass it as a reference in the headers.
Post Read Action	Select what happens to a message after it has been read: <ul style="list-style-type: none"> <li>• <b>Archive</b> - The message is archived.</li> <li>• <b>Delete</b> - The message is deleted.</li> </ul>

Option	To create or edit...
Stage Directory	Enter an intermediate directory to temporarily stage the files while processing them. Do not put the stage directory inside of the polling directory (the directory identified in the URL of the file transport proxy service; for example, file:///c:/dir1/dir2).
Archive Directory	Specify the path to the archive location if the <b>Post Read Action</b> option is set to <b>Archive</b> . The Archive Directory field is also a required field if you have selected the Pass By Reference field. Do not put the archive directory inside of the polling directory.
Error Directory	Enter the location where messages and attachments are posted if there is a problem. Do not put the error directory inside of the polling directory.
Request Encoding	Accept the default UTF-8 as the character set encoding for requests in file transports, or enter a different character set encoding.

## FTP Transport Configuration page (Business Services)

Use this page to configure transport settings for a business service using the ftp transport protocol.

Option	To create or edit...
User Authentication	Select <b>anonymous</b> if the user of the FTP server is anonymous, or select <b>external user</b> if the user of the FTP server is an externally configured account.
Identity (E-mail id)	This field is available only if the <b>User Authentication</b> option is set to <b>anonymous</b> . Enter the mail ID for the anonymous user.
Service Account	This field is available only if the <b>User Authentication</b> option is set to <b>external user</b> . Enter the service account for the external user.
Timeout	Enter the socket timeout interval, in seconds, before the connection is dropped. The default is 60 seconds.
Prefix for destination File Name	Enter a prefix for the file name under which the file is stored on the remote server. Do not enter * in this field. This character causes a run-time exception.

Option	To create or edit...
Suffix for destination File Name	Enter a suffix for the file name under which the file is stored on the remote server. Do not enter * in this field. This character causes a run-time exception.
Transfer Mode	Select <b>ASCII</b> or <b>binary</b> as the transfer mode.
Request Encoding	Accept the default UTF-8 as the character set encoding for requests in ftp transports, or enter a different character set encoding.

## FTP Transport Configuration page (Proxy Services)

Use this page to configure transport settings for a proxy service using the ftp transport protocol.

Option	To create or edit...
User Authentication	Select <b>anonymous</b> if the user of the FTP server is anonymous, or select <b>external user</b> if the user of the FTP server is an externally configured account.
Identity (E-Mail ID)	This field is available only if the <b>User Authentication</b> option is set to <b>anonymous</b> . Enter the mail ID for the anonymous user.
Service Account	This field is available only if the <b>User Authentication</b> option is set to <b>external user</b> . Enter the service account for the user. This is a required field when the <b>User Authentication</b> option is set to <b>external user</b> .
Pass By Reference	Select this check box to stage the file in the archive directory and pass it as a reference in the headers.
Remote Streaming	Select this check box to stream the FTP files directly from the remote server at the time of processing. When you select this option, the archive directory is the remote directory on the remote FTP server machine. Therefore, you should specify the archive directory as relative to the FTP user directory.
File Mask	Enter the regular expression for the files to be picked. The default is *.*.*.
Managed Server	Select the Managed Server for polling in a clustered domain. This field is available <i>only</i> in a clustered domain.
Polling Interval	Enter a polling interval, in seconds. The default is 60.

Option	To create or edit...
Read Limit	Specify the maximum number of messages to read per polling sweep. Enter 0 to specify no limit. The default is 10.
Post Read Action	Select what happens to a message after it has been read. <ul style="list-style-type: none"> <li>• <b>Archive</b> - The message is archived.</li> <li>• <b>Delete</b> - The message is deleted.</li> </ul>
Transfer Mode	Select <b>ASCII</b> or <b>binary</b> as the transfer mode.
Archive Directory	Specify the path to the archive location if the <b>Post Read Action</b> option is set to <b>Archive</b> . This field is required if the <b>Pass By Reference</b> option is selected. <p><b>Note:</b> The Archive, Download, and Error directories are absolute paths, and they are automatically created. If you specify a relative path, the files are created relative to the Java process that starts the WebLogic Server.</p>
Download Directory	Enter the directory on your local machine where files are downloaded during the file transfer. <p><b>Note:</b> The Archive, Download, and Error directories are absolute paths, and they are automatically created. If you specify a relative path, the files are created relative to the Java process that starts the WebLogic Server.</p>
Error Directory	Enter the location where messages are posted if there is a problem. <p><b>Note:</b> The Archive, Download, and Error directories are absolute paths, and they are automatically created. If you specify a relative path, the files are created relative to the Java process that starts the WebLogic Server.</p>
Request Encoding	Accept the default UTF-8 as the character set encoding for requests in FTP transports.
<b>Advanced Settings</b>	
Scan Subdirectories	Select this check box to recursively scan all directories
Sort By Arrival	Select this check box to deliver events in the order of arrival.
Timeout	Enter the socket timeout interval, in seconds, before the connection is dropped. If you enter 0, there is no timeout.
Retry Count	Specify the number of retries for FTP connection failures.

## HTTP Transport Configuration Page (Business Services)

Use this page to configure transport settings for a business service using the HTTP transport protocol. The HTTP transport supports both HTTP and HTTPS endpoints.

Option	To create or edit...
Timeout	Enter the timeout interval, in seconds, before the connection is dropped. If you enter 0, there is no timeout.
HTTP Request Method	<p>Select <b>POST</b> or <b>GET</b> as the HTTP request method header for sending a message.</p> <p>The GET method can include as part of the request some of its own information that better describes what to get. This information is passed as a sequence of characters appended to the request URL in a query string. The POST method passes all its data, of unlimited length, directly over the socket connection as part of its HTTP request body. The exchange is invisible to the client, and the URL doesn't change at all.</p>
Authentication	<p>Select one of the following:</p> <ul style="list-style-type: none"> <li>• <b>None</b> - Specifies that authentication is not required to access this service.</li> <li>• <b>Basic</b> - Specifies that basic authentication is required to access this service.</li> </ul> <p>Basic authentication instructs WebLogic Server to authenticate the client using a user name and password against the authentication providers configured in the security realm, such as a Lightweight Directory Access Protocol (LDAP) directory service and Windows Active Directory. The client must send its user name and password on the HTTP request header.</p> <p>Basic authentication is strongly discouraged over HTTP because the password is sent in clear text. However, it is safe to send passwords over HTTPS because HTTPS provides an encrypted channel.</p> <p><b>Warning:</b> By default, all users (authorized and anonymous) can access a business service. To limit the users who can access a business service, create a transport-level authorization policy. To access a proxy service, create a transport-level authorization policy. See "Editing Transport-Level Access Policies" under <a href="#">Security Configuration</a> in the <i>Using the AquaLogic Service Bus Console</i>.</p> <p><b>Client Certificate</b> - Specifies encrypted communication and strong client authentication (two-way SSL). To learn more, see <a href="#">Configuring Transport-Level Security</a> in the <i>AquaLogic Service Bus Security Guide</i>.</p>

Option	To create or edit...
Service Account	<ul style="list-style-type: none"> <li>Enter a service account. A service account is an alias resource for a user name and password. This is a required field if you selected the <b>Basic Authentication Required</b> field.</li> </ul>
Follow HTTP redirects	<p>Select this check box to specify that HTTP redirects (which are requests with a response code 3xx) should be automatically followed. A re-direct occurs when you send an outbound request to the URL of a business service, and that service returns a response code (for example, 302) that says the URL is no longer valid and this request needs to be sent to another URL. If the <b>Follow HTTP Redirects</b> check box is selected, ALSB automatically re-sends the request to the new URL without any action on your part. Deselect this check box if you do not want the HTTP redirects to be automatically followed.</p>
Dispatch Policy	<p>Select the instance of WebLogic Server Work Manager that you want to use for the dispatch policy for this endpoint. The default Work Manager is used if no other Work Manager exists. For information about Work Managers, see <a href="#">Using Work Managers to Optimize Scheduled Work</a> and <a href="#">Create Work Manager</a> in the <i>WebLogic Server Administration Console Online Help</i>.</p>
Request Encoding	<p>Accept the default <code>iso-8859-1</code> as the character set encoding for requests in HTTP transports, or enter a different character set encoding.</p>
Response Encoding	<p>Accept the default <code>iso-8859-1</code> as the character set encoding for responses in HTTP transports, or enter a different character set encoding.</p>

## HTTP Transport Configuration Page (Proxy Services)

Use this page to configure transport settings for a proxy service using the HTTP transport protocol. The HTTP transport supports both HTTP and HTTPS endpoints.

Option	To create or edit...
HTTPS required	<p>Select this check box for inbound HTTPS endpoints.</p> <p>To learn more, see <a href="#">Configuring Transport-Level Security</a> in the <i>AquaLogic Service Bus Security Guide</i>.</p>
Authentication	<p>Select one of the following:</p> <ul style="list-style-type: none"> <li>• <b>None</b> - Specifies that authentication is not required.</li> <li>• <b>Basic</b> - Specifies that basic authentication is required to access this service.           <p>Basic authentication instructs WebLogic Server to authenticate the client using a user name and password against the authentication providers configured in the security realm, such as a Lightweight Directory Access Protocol (LDAP) directory service and Windows Active Directory. The client must send its user name and password on the HTTP request header.</p> <p>Basic authentication is strongly discouraged over HTTP because the password is sent in clear text. However, it is safe to send passwords over HTTPS because HTTPS provides an encrypted channel.</p> <p><b>Warning:</b> By default, all users (authorized and anonymous) can access a proxy service. To limit the users who can access a proxy service, create a transport-level authorization policy. See “Editing Transport-Level Access Policies” under <a href="#">Security Configuration</a> in the <i>Using the AquaLogic Service Bus Console</i>.</p> </li> <li>• <b>Client Certificate</b> - Specifies encrypted communication and strong client authentication (two-way SSL). To learn more, see <a href="#">Configuring Transport-Level Security</a> in the <i>AquaLogic Service Bus Security Guide</i>.</li> <li>• <b>Custom Authentication</b> - Specifies that an authentication token is contained in an HTTP header. The client's identity is established through the use of this client-supplied token. You must configure an Identity Assertion provider that maps the token to an ALSB user.           <p>The custom authentication token can be of any active token type supported by a configured WebLogic Server Identity Assertion provider.</p> </li> </ul>

Option	To create or edit...
Dispatch Policy	<p>Select a dispatch policy for this endpoint. Leave blank to use the default dispatch policy.</p> <p>Dispatch policy refers to the instance of WLS Work Manager that you want to use for the service endpoint. For information about Work Managers, see <a href="#">Using Work Managers to Optimize Scheduled Work</a> and <a href="#">Create Work Manager</a> in the <i>WebLogic Server Administration Console Online Help</i>.</p>
Request Encoding	<ul style="list-style-type: none"> <li>For HTTP inbound transports:           <p>If the character set encoding parameter of the <code>Content-Type</code> header is not specified in Client Request, enter a character set encoding parameter. If you do not enter a value, the field defaults to <code>ISO-8859-1</code>.</p> </li> <li>For HTTP outbound transports:           <p>If you have not configured a request encoding, the ALSB run time decides the most appropriate encoding while it makes a request to the business service. In the case of a non-passthrough scenario, the default character encoding is <code>UTF-8</code> at run time. However if it is a passthrough scenario, the run time will pass through the encoding received with the outbound response.</p> </li> </ul>
Response Encoding	<p>Accept the default <code>ISO-8859-1</code> as the character set encoding for responses in HTTP transports, or enter a different character set encoding.</p>
<b>Advanced Settings</b>	
Authentication Header	<p>Enter the HTTP header (any except <code>Authorization</code>) from which ALSB is to extract the token. This field is available only if you selected the <b>Custom Authentication</b> check box.</p> <p>For example, <code>client-xyz-token</code>.</p>
Authentication Token Type	<p>Select an authentication token type. Only the active token types configured for an Identity Assertion provider are available. (See “Configuring Identity Assertion Providers” under <a href="#">Configuring Custom Authentication</a> in the <i>AquaLogic Service Bus Security Guide</i> for more information.) This field is available only if you selected the <b>Custom Authentication</b> check box.</p>

## JMS Transport Configuration page (Business Services)

Use this page to configure transport settings for a business service using the JMS transport protocol. For more information, see the [AquaLogic Service Bus Interoperability Solutions for JMS and WebSphere MQ](#).

Option	To create or edit...
Destination Type	Select a type for the JMS bridge destination: <ul style="list-style-type: none"> <li>• <b>Queue</b> (for point-to-point)</li> <li>• <b>Topic</b> (for publish/subscribe)</li> </ul>
Message Type	Select one of the following: <ul style="list-style-type: none"> <li>• <b>Bytes</b> (for a stream of uninterpreted bytes)</li> <li>• <b>Text</b> (for text messages)</li> </ul>
Is Response Required	This option is available only when <b>Queue</b> is selected for the <b>Destination Type</b> . Select this option to specify that a response is expected after an outbound message is sent.
Response Correlation Pattern	This option is available only when the <b>Is Response Required</b> check box is selected. Select one of the following: <ul style="list-style-type: none"> <li>• Select <b>JMSMessageID</b> for JAX-RPC services running on WebLogic Server 9.2.</li> <li>• Select <b>JMSCorrelationID</b> for all other services. When you select this option, you must also enter a <b>Response URI</b>, below.</li> </ul>
Response URI	This option is available only when <b>JMSCorrelationID</b> is selected for the <b>Response Correlation Pattern</b> . Enter a response URI in the format: <pre>jms://host:port/factoryJndiName/destJndiName</pre> To target multiple servers, use the following format: <pre>jms://host1:port,host2:port/QueueConnectionFactory/DestName</pre>
Response Connection Factory	This option is available only when <b>JMSMessageID</b> is selected for the <b>Response Correlation Pattern</b> . Enter enter a response connection factory URI. If a connection factory is not specified, the connection factory for the request is used for the response.

Option	To create or edit...
Response JNDI Names	<p>This option is available only when <b>JMSMessageID</b> is selected for the <b>Response Correlation Pattern</b>.</p> <p>Enter a list of JNDI destination names</p>
Response Timeout	<p>Enter the amount of time to wait for the response, in seconds. This field is required if you selected <b>Is Response Required</b>.</p>
Request Encoding	<p>Accept the default UTF-8 as the character set encoding for requests in JMS transports, or enter a different character set encoding.</p>
Response Encoding	<p>This option is available only when the <b>Is Response Required</b> check box is selected.</p> <p>Accept the default UTF-8 as the character set encoding for responses in JMS transports, or enter a different character set encoding.</p>
Dispatch Policy	<p>Select the instance of WebLogic Server Work Manager that you want to use for the dispatch policy for this endpoint. The default Work Manager is used if no other Work Manager exists.</p> <p>For example, if the business service has a JMS transport protocol, the business service endpoint is an MDB (message-driven bean) JAR file that you can associate with the specific dispatch policy.</p>
<b>Advanced Settings</b>	
Use SSL	<p>Select only if the requests are made over a TLS/SSL connection.</p> <p>TLS/SSL (Secure Sockets Layer) provides secure connections by allowing two applications connecting over a network to authenticate the other's identity and by encrypting the data exchanged between the applications. Authentication allows a server, and optionally a client, to verify the identity of the application on the other end of a network connection. Additionally, if the administrator has restricted access to individual JMS destinations (queues or topics) by setting access control on the JNDI entry for the destination, the Business Service must authenticate when looking up the entry in the JNDI tree with a user name and password.</p>
Expiration	<p>The time interval in milliseconds after which the message will expire. Default value is 0, which means that the message never expires.</p>

Option	To create or edit...
Unit of Order	Enter a message unit-of-order. Message unit-of-order enables message producers to group messages into a single unit with respect to the processing order. This single unit-of-order requires that all messages in that unit be processed sequentially in the order they were created.
JNDI Service Account	Select a service account to use for JNDI lookups. To learn more about service accounts, see <a href="#">“Service Accounts” on page 14-1</a> .
JMS Service Account	Select a service account to use for the JMS resource managed by the JMS server. A service account is an alias resource for a User ID and its associated password.  For more information: <ul style="list-style-type: none"> <li>• <a href="#">“Service Accounts” on page 14-1</a></li> <li>• <a href="#">“Adding Service Accounts” on page 14-4</a></li> </ul>

## JMS Transport Configuration page (Proxy Services)

Use this page to configure transport settings for a proxy service using the JMS transport protocol. For more information, see the [AquaLogic Service Bus Interoperability Solutions for JMS and WebSphere MQ](#).

Option	To create or edit...
Destination Type	Select one of the following: <ul style="list-style-type: none"> <li>• <b>Queue</b> (for a point-to-point destination type)</li> <li>• <b>Topic</b> (for a publish/subscribe destination)</li> </ul>
Is Response Required	This option is available only when <b>Queue</b> is selected for the <b>Destination Type</b> .  Select this option to specify that a response is expected after an outbound message is sent.

Option	To create or edit...
Response Correlation Pattern	<p>This option is available only when the <b>Is Response Required</b> check box is selected.</p> <p>Select one of the following:</p> <ul style="list-style-type: none"> <li>• Select <b>JMSMessageID</b> for JAX-RPC services running on WebLogic Server 9.2.</li> <li>• Select <b>JMSCorrelationID</b> for all other services. When you select this option, you must also enter a <b>Response URI</b>, below.</li> </ul>
Response URI	<p>This option is available only when <b>JMSCorrelationID</b> is selected for the <b>Response Correlation Pattern</b>.</p> <p>Enter a response URI in the format:</p> <pre data-bbox="491 725 1096 748">jms://host:port/factoryJndiName/destJndiName</pre> <p>To target multiple servers, use the following format:</p> <pre data-bbox="462 800 1150 852">jms://host1:port,host2:port/QueueConnectionFactory/DestName</pre>
Response Connection Factory	<p>This option is available only when <b>JMSMessageID</b> is selected for the <b>Response Correlation Pattern</b>.</p> <p>Enter enter a response connection factory URI.</p> <p>If a connection factory is not specified, the connection factory for the request is used for the response.</p>
Response Message Type	<p>This option is available only when the <b>Is Response Required</b> check box is selected.</p> <p>Select one of the following:</p> <ul style="list-style-type: none"> <li>• <b>Bytes</b> (for a stream of uninterpreted bytes)</li> <li>• <b>Text</b> (for text messages)</li> </ul>
Request Encoding	<p>Accept the default UTF-8 as the character set encoding for requests in JMS transports, or enter a different character set encoding.</p>
Response Encoding	<p>This option is available only when the <b>Is Response Required</b> check box is selected.</p> <p>Accept the default UTF-8 as the character set encoding for responses in JMS transports, or enter a different character set encoding.</p>

Option	To create or edit...
Client Response Timeout	<p>This option is available only when the <b>Is Response Required</b> check box is selected.</p> <p>Enter the number of seconds to wait for a server response before dropping the connection. This only applies if the client is another proxy service in the same domain.</p>
Dispatch Policy	<p>Select a dispatch policy for this endpoint. <b>Default</b> signifies the default dispatch policy.</p> <p>Dispatch policy refers to the instance of WLS Work Manager that you want to use for the service endpoint to process the request. For example, if the proxy service has a JMS transport protocol, the proxy service endpoint is an MDB (message-driven bean) JAR file that you can associate with the specific dispatch policy.</p>
<b>Advanced Settings</b>	
Use SSL	<p>Select only if the requests are made over a TLS/SSL connection.</p> <p>TLS/SSL (Secure Sockets Layer) provides secure connections by allowing two applications connecting over a network to authenticate the other's identity and by encrypting the data exchanged between the applications. Authentication allows a server, and optionally a client, to verify the identity of the application on the other end of a network connection. Additionally, if the administrator has restricted access to individual JMS destinations (queues or topics) by setting access control on the JNDI entry for the destination, the Business Service must authenticate when looking up the entry in the JNDI tree with a user name and password.</p>
Message Selector	<p>Enter a message selector expression.</p> <p>Only messages with properties matching the expression are processed</p>
Durable Subscription	<p>This option is available only if <b>Topic</b> is selected for the <b>Destination Type</b>.</p> <p>Select this check box if the subscription is durable or leave it blank if the subscription is not durable</p>
Retry Count	<p>Enter the number of delivery retries a message can have before it is moved to the error destination. This field only applies to WebLogic Server JMS destinations.</p>

Option	To create or edit...
Retry Interval	Enter the amount of time, in milliseconds, before rolled back or recovered messages are redelivered. This field only applies to WebLogic Server JMS destinations.
Error Destination	Enter the name of the target destination for messages that have reached their redelivery limit. This field only applies to WebLogic Server JMS destinations.
Expiration Policy	Select an Expiration Policy to use when an expired message is encountered on a destination. This field only applies to WebLogic Server JMS destinations.
Is XA Required	Select this check box if your connection factory is XA. This value is into account when the remote connection factory is unavailable. If your connection factory is available and this value is true, make sure that the connection factory is defined as transactional.
JMS Service Account	Select a service account to use for the JMS resource managed by the JMS server. A service account is an alias resource for a User ID and its associated password. To learn more about service accounts, see <a href="#">“Service Accounts” on page 14-1</a> .

## JPD Transport Configuration page (Business Services)

Use this page to configure transport settings for a business service using the JPD transport protocol. For more information about the JPD transport, see the [JPD Transport User Guide](#).

Option	To create or edit...
System Service Account	<p>Enter the service account for the user, or click <b>Browse</b> to select one from the list displayed.</p> <p>The system service account specifies the user credentials for the invocation of the WLI stateless session bean that the JPD transport uses to send incoming messages.</p> <p>If no service account is specified, the inbound request subject is used. If there is no inbound request subject, an anonymous subject is used.</p>
Process Service Account	<p>Enter the service account for the user, or click <b>Browse</b> to select one from the list displayed.</p> <p>The process service account specifies the user credentials for the invocation of the JPD.</p> <p>If no service account is specified, the inbound request subject is used. If there is no inbound request subject, an anonymous subject is used.</p>
Callback Proxy Location	<p>Enter the location of the proxy service for receiving callbacks from the JPD, specified in the following format:</p> <pre>jms://[host:port[,host:port]*]/MyFactory/MyQueue</pre> <p>Where:</p> <ul style="list-style-type: none"> <li>• <b>host</b>: (optional) Host name of the ALSB server where the callback proxy service is configured</li> <li>• <b>port</b>: (optional) Port number on which ALSB is listening for incoming requests</li> <li>• <b>MyFactory</b>: JNDI name of the Queue connection factory</li> <li>• <b>MyQueue</b>: JNDI name of the Queue where the ALSB proxy service is waiting for callback requests</li> </ul> <p>In a clustered environment, specify the host name and port numbers of the Managed Servers, separated by a comma (.).</p> <p>The Callback Proxy Location will be ignored if the JPD being invoked is a synchronous JPD or an asynchronous JPD without callbacks.</p>

Option	To create or edit...
Dispatch Policy	Select the default dispatch policy or a configured Work Manager instance for the outbound response. For information about Work Managers, see <a href="#">Using Work Managers to Optimize Scheduled Work</a> and <a href="#">Create Work Manager</a> in the WebLogic Server <i>Administration Console Online Help</i> .
Propagate Transaction	Select the check box to propagate the existing transaction within ALSB to the JPD.

## MQ Transport Configuration page (Business Services)

Before you use the MQ transport, you must configure a MQ Connection resource. See [Working with MQ Connections](#). For more information about the MQ transport, see the [Native MQ Transport User Guide](#).

Use this page to configure transport settings for a proxy service using the native MQ transport protocol.

Option	To create or edit...
Is Response Required	Select this option to specify that a response is expected after an outbound message is sent.
Polling Interval	This option is available only when the <b>Is Response Required</b> check box is selected.  Enter a polling interval, in milliseconds. The default is 1000.
Response Message Type	This option is available only when the <b>Is Response Required</b> check box is selected.  Select one of the following: <ul style="list-style-type: none"> <li>• <b>Bytes</b> (for a stream of uninterpreted bytes)</li> <li>• <b>Text</b> (for text messages)</li> </ul>
Response Correlation Pattern	This option is available only when the <b>Is Response Required</b> check box is selected.  Specify whether the response correlation pattern should be based on <b>MessageID</b> or <b>CorrelationID</b> .

Option	To create or edit...
Auto-generate Correlation Value	Select this check box to automatically generate a CorrelationID or MessageID.
Response URI	<p>This option is available only when the <b>Is Response Required</b> check box is selected.</p> <p>The destination to which the response should be published. Enter a response URI in the same format as the endpoint URI:  <code>mq://&lt;local-queue-name&gt;?conn=&lt;mq-connection-resource-ref&gt;</code></p> <p>For more detailed information, see the <a href="#">Native MQ Transport User Guide</a>.</p>
Response Timeout	<p>This option is available only when the <b>Is Response Required</b> check box is selected.</p> <p>Enter the number of seconds to wait for a response before dropping the connection.</p>
Dispatch Policy	<p>This option is available only when the <b>Is Response Required</b> check box is selected.</p> <p>Select a dispatch policy for this endpoint or use the default dispatch policy.</p> <p>Dispatch policy refers to the instance of WLS Work Manager that you want to use for the service endpoint. For more information, see “Creating a Work Manager” in the <a href="#">Native MQ Transport User Guide</a>.</p>

## MQ Transport Configuration page (Proxy Services)

Before you use the MQ transport, you must configure a MQ Connection resource. See [Working with MQ Connections](#). For more information about the MQ transport, see the [Native MQ Transport User Guide](#).

Use this page to configure transport settings for a proxy service using the native MQ transport protocol.

Option	To create or edit...
Polling Interval	Enter a polling interval, in milliseconds. The default is 1000.
Is Response Required	Select this option to specify that a response is expected after an outbound message is sent.

Option	To create or edit...
Response Correlation Pattern	<p>This option is available only when the <b>Is Response Required</b> check box is selected.</p> <p>Specify whether the response correlation pattern should be based on <b>MessageID</b> or <b>CorrelationID</b>.</p>
MQ Response URI	<p>This option is available only when the <b>Is Response Required</b> check box is selected.</p> <p>The destination to which the response should be published. Enter a response URI in the same format as the endpoint URI:  <code>mq://&lt;local-queue-name&gt;?conn=&lt;mq-connection-resource-ref&gt;</code></p> <p>For more detailed information, see the <a href="#">Native MQ Transport User Guide</a>.</p>
Response Message Type	<p>This option is available only when the <b>Is Response Required</b> check box is selected.</p> <p>Select one of the following:</p> <ul style="list-style-type: none"> <li>• <b>Bytes</b> (for a stream of uninterpreted bytes)</li> <li>• <b>Text</b> (for text messages)</li> </ul>
Client Response Timeout	<p>This option is available only when the <b>Is Response Required</b> check box is selected.</p> <p>Enter the number of seconds to wait for a response before dropping the connection.</p>
Dispatch Policy	<p>This option is available only when the <b>Is Response Required</b> check box is selected.</p> <p>Select a dispatch policy for this endpoint or use the default dispatch policy.</p> <p>Dispatch policy refers to the instance of WLS Work Manager that you want to use for the service endpoint. For more information, see “Creating a Work Manager” in the <a href="#">Native MQ Transport User Guide</a>.</p>

## SB Transport Configuration page (Business Services)

Use this page to configure transport settings for a proxy service using the SB (Service Bus) transport protocol. For more information about the SB transport, see the [SB Transport User Guide](#).

Option	To create or edit...
Dispatch policy	Select the instance of WebLogic Server Work Manager that you want to use for the dispatch policy for this endpoint. The default Work Manager is used if no other Work Manager exists. For information about Work Managers, see <a href="#">Using Work Managers to Optimize Scheduled Work</a> and <a href="#">Create Work Manager</a> in the WebLogic Server <i>Administration Console Online Help</i> .
Timeout	The amount of time in seconds it takes the service to time out.  <b>Note:</b> The timeout will be ignored when the quality of service is Exactly-Once.
Service Account	<ul style="list-style-type: none"> <li>Click <b>Browse</b> and select a service account from the list displayed. If no service account is specified, an anonymous subject is used.</li> </ul>

## SB Transport Configuration page (Proxy Services)

Use this page to configure transport settings for a proxy service using the SB (Service Bus) transport protocol. For more information about the SB transport, see the [SB Transport User Guide](#).

Option	To create or edit...
Dispatch Policy	Select a dispatch policy for this endpoint or use the default dispatch policy.  Dispatch policy refers to the instance of WLS Work Manager that you want to use for the service endpoint to process the request. For information about Work Managers, see <a href="#">Using Work Managers to Optimize Scheduled Work</a> and <a href="#">Create Work Manager</a> in the WebLogic Server <i>Administration Console Online Help</i> .
Use SSL	When specified, requests must be sent over an SSL connection.  However, unsecured connections are not forbidden. The administrator must close all unsecured protocols on the server (for example, t3 or http) to strictly enforce secured client connections.

## SFTP Transport Configuration page (Business Services)

Use this page to configure transport settings for a proxy service using the sftp transport protocol. For more information about the SFTP transport, see the [SFTP Transport User Guide](#).

Option	To create or edit...
User Authentication	<p>Select one of the following:</p> <ul style="list-style-type: none"> <li>• <b>Username Password Authentication</b> - Specifies that a static service account is associated with this authentication method and the client is authenticated using the provided credentials.</li> <li>• <b>Host Based Authentication</b> - Specifies that a user name and service key provider is required to use this authentication method. Any user connecting from a known host is authenticated using the private key of the host.</li> <li>• <b>Public Key Authentication</b> - Specifies that a user name and service key provider is required to use this authentication method. Every user has their own private key.</li> </ul>
Service Account	Enter the service account for the user, or click <b>Browse</b> to select service accounts from a browser.
Service Key Provider	<p>This option is available only when <b>Host Based</b> or <b>Public Key Authentication</b> is selected.</p> <p>Enter a service key provider in the <b>Service Key Provider</b> field. You can click <b>Browse</b> to select service key providers from a browser. This is a required field.</p>
Username	<p>This option is available only when <b>Host Based</b> or <b>Public Key Authentication</b> is selected.</p> <p>Enter the user name.</p>
Timeout	Enter the socket timeout interval, in seconds, before the connection is dropped. If you enter 0, there is no timeout. The default value is 60.
Prefix for destination File Name	Enter the prefix for the file name under which the file is stored on the remote server.
Suffix for destination File Name	Enter the suffix for the file name under which the file is stored on the remote server.
Request Encoding	Accept the default UTF-8 as the character set encoding for requests in SFTP transports.

## SFTP Transport Configuration page (Proxy Services)

Use this page to configure transport settings for a proxy service using the sftp transport protocol. For more information about the SFTP transport, see the [SFTP Transport User Guide](#).

Option	To create or edit...
User Authentication	<p>Select one of the following:</p> <ul style="list-style-type: none"> <li>• <b>Username Password Authentication</b> - Specifies that a static service account is associated with this authentication method and the client is authenticated using the provided credentials.</li> <li>• <b>Host Based Authentication</b> - Specifies that a user name and service key provider is required to use this authentication method. Any user connecting from a known host is authenticated using the private key of the host.</li> <li>• <b>Public Key Authentication</b> - Specifies that a user name and service key provider is required to use this authentication method. Every user has their own private key.</li> </ul>
Service Account	Enter the service account for the user, or click <b>Browse</b> to select service accounts from a browser.
Service Key Provider	<p>This option is available only when <b>Host Based</b> or <b>Public Key Authentication</b> is selected.</p> <p>Enter a service key provider in the <b>Service Key Provider</b> field. You can click <b>Browse</b> to select service key providers from a browser. This is a required field.</p>
Username	<p>This option is available only when <b>Host Based</b> or <b>Public Key Authentication</b> is selected.</p> <p>Enter the user name.</p>
Pass By Reference	Select this check box to stage the file in the archive directory and pass it as a reference in the headers.
Remote Streaming	Select this check box to stream the SFTP files directly from the remote server at the time of processing. When you select this option, the archive directory is the remote directory on the remote SFTP server machine. Therefore, you should specify the archive directory as relative to the SFTP user directory.
File Mask	Enter the regular expression for the files to be picked. The default is *.*.

Option	To create or edit...
Managed Server	<p>This field is available only in a clustered domain.</p> <p>Select the Managed Server to act as the polling server. All of the Managed Servers can process the message, but only one can poll for the message.</p>
Polling Interval	<p>Enter the interval in seconds at which the file is polled from the specified location. The default is 60.</p>
Read Limit	<p>Specify the maximum number of messages to read per polling sweep. Enter 0 to specify no limit. The default is 10.</p>
Post Read Action	<p>Select what happens to a message after it has been read.</p> <ul style="list-style-type: none"> <li>• <b>Archive</b> - The message is archived.</li> <li>• <b>Delete</b> - The message is deleted.</li> </ul>
Archive Directory	<p>Specify the path to the archive location if the <b>Post Read Action</b> option is set to <b>Archive</b>. This field is required if the <b>Pass By Reference</b> option is selected.</p> <p><b>Note:</b> The Archive, Download, and Error directories are absolute paths, and they are automatically created. If you specify a relative path, the files are created relative to the Java process that starts the WebLogic Server.</p>
Download Directory	<p>Enter the directory on your local machine where files are downloaded during the file transfer.</p> <p><b>Note:</b> The Archive, Download, and Error directories are absolute paths, and they are automatically created. If you specify a relative path, the files are created relative to the Java process that starts the WebLogic Server.</p>
Error Directory	<p>Enter the location where messages are posted if there is a problem.</p> <p><b>Note:</b> The Archive, Download, and Error directories are absolute paths, and they are automatically created. If you specify a relative path, the files are created relative to the Java process that starts the WebLogic Server.</p>
Request Encoding	<p>Accept the default UTF-8 as the character set encoding for requests in SFTP transports.</p>
<b>Advanced Settings</b>	
Scan Subdirectories	<p>Select this check box to recursively scan all directories</p>
Sort By Arrival	<p>Select this check box to deliver events in the order of arrival.</p>

Option	To create or edit...
Timeout	Enter the socket timeout interval, in seconds, before the connection is dropped. If you enter 0, there is no timeout. The default value is 60.
Retry Count	Specify the number of retries for SFTP connection failures.

## Tuxedo Transport Configuration page (Business Services)

Use this page to configure transport settings for a proxy service using the Tuxedo transport protocol. For more information about the Tuxedo transport, see [AquaLogic Service Bus Interoperability Solution for Tuxedo](#).

Option	To create or edit...
Field Table Classes	Enter the name of the class or classes describing the FML/FML32 buffer received. These are used for the FML/FML32-to-XML conversion routines to map field names to element names. This is a space separated list of fully qualified class names.
View Classes	Enter the name of the class or classes describing the VIEW/VIEW32 buffer received or sent. These are used for the VIEW-to-XML or VIEW32-to-XML conversion routines to map field names to element names. This is a space separated list of fully qualified class names.
Classes Jar	Select a JAR Resource that contains a JAR file with the FML/FML32 or VIEW/VIEW32 classes necessary for this endpoint operation.
Remote Access Point(s)	<p>Select a remote access point from the drop down list that is associated with the Import. The list contains remote access points configured in WTC. A business service cannot be created if there is no associated remote access point.</p> <p>If no remote access points exist or to create a new one, select <b>New</b>. Enter the corresponding <b>Access Point Name</b> and <b>Network Address</b> in the adjacent fields. Upon validation of the endpoint, the access point is added to the WTC configuration for each WTC server. If no WTC server exists, one is created.</p> <p>If more than one URI has been specified, there will be one remote access point field per URI and the URI displays for informative purposes. If more than one URI exists, each requires a different remote access point. If the URI specified already corresponds to an existing WTC resource, the corresponding remote access point displays, but cannot be modified.</p>

Option	To create or edit...
Local Access Point(s)	<p>This field appears only when you select <b>New</b> in the <b>Remote Access Point</b> field.</p> <p>From the drop-down list, select a local access point to be associated with the newly created remote access point. If none exist or to create a new one, select <b>New</b>. Enter the corresponding <b>Local Access Point Name</b> and <b>Local Network Address</b> in the adjacent fields.</p>
Request Buffer Type	<p>Select the type of buffer that the remote Tuxedo service will receive.</p>
Request Buffer Subtype	<p>This option is enabled if the previous <b>Request Buffer Type</b> value is VIEW or VIEW32. Enter the buffer subtype with which to associate the request buffer.</p>
Response Required?	<p>Select this check box to indicate a bidirectional call. If not checked, the underlying <code>tpcall</code> is invoked with <code>TPNOREPLY</code> flag, and a null response is posted asynchronously.</p>
Suspend Transaction?	<p>Select this check box to suspend the transaction, if it exists. This is useful when the remote service does not support transactions.</p>
Dispatch Policy	<p>Select the instance of WebLogic Server Work Manager that you want to use for the dispatch policy for this endpoint. The default Work Manager is used if no other Work Manager exists.</p> <p>This Work Manager is used to asynchronously post a null reply in the case of a one-way invocation. For information about Work Managers, see <a href="#">Using Work Managers to Optimize Scheduled Work</a> and <a href="#">Create Work Manager</a> in the <i>WebLogic Server Administration Console Online Help</i>.</p>
Request Encoding	<p>Specify a character set encoding for requests in Tuxedo transports.</p>
Response Encoding	<p>Specify a character set encoding for responses in Tuxedo transports.</p>

Option	To create or edit...
Timeout	Specify the maximum amount of time (in seconds) that the transport run time waits for replies; an integer value that is greater than or equal to 0. If not specified or set to zero (default), replies will time out at BLOCKTIME, the maximum number of seconds that the local WTC access point allows for a blocking call.
Transformation Style	Select one of the following: <ul style="list-style-type: none"> <li>• <b>None</b> - (default) The order of fields may not be respected.</li> <li>• <b>Ordered</b> - The fields are presented with all their occurrences in the correct order.</li> <li>• <b>Ordered and Grouped</b> - If the fields are logically structured as records, the fields are ordered by occurrence and grouped by record.</li> </ul>

## Tuxedo Transport Configuration page (Proxy Services)

Use this page to configure transport settings for a proxy service using the Tuxedo transport protocol. For more information about the Tuxedo transport, see [AquaLogic Service Bus Interoperability Solution for Tuxedo](#).

Option	To create or edit...
Field Table Classes	Enter the name of the class or classes describing the FML/FML32 buffer received. These are used for the FML/FML32-to-XML conversion routines to map field names to element names. This is a space separated list of fully qualified class names.
View Classes	Enter the name of the class or classes describing the VIEW/VIEW32 buffer received or sent. These are used for the VIEW-to-XML or VIEW32-to-XML conversion routines to map field names to element names. This is a space separated list of fully qualified class names.  X_C_TYPE and X_COMMON Tuxedo buffer types are handled in the same manner as VIEW/VIEW32 buffers.  If an incoming request contains a VIEW, then the corresponding VIEW class should be specified in the ALSB CLASSPATH.
Classes Jar	Select a JAR resource that contains a JAR file with the FML/FML32 or VIEW/VIEW32 classes necessary for this endpoint operation.

Option	To create or edit...
Local Access Point	<p>Select a local access point from the drop-down list that is associated with the export. The drop-down list contains local access points configured in WTC. A proxy service cannot be created if there is not an associated local access point.</p> <p>If no local access points exist or to create a new one, select <b>New</b>. Enter the corresponding <b>Local Access Point Name</b> and <b>Local Network Address</b> in the adjacent fields. Upon validation of the endpoint, the access point is added to the WTC configuration for each WTC server. If no WTC server exists, one is created.</p> <p>You can enter an existing access point name after selecting the <b>New</b> option. This causes the existing information to be updated with the new parameters. You can change only the host name and port number.</p>
Remote Access Point	<p>This field appears only when you select <b>New</b> in the <b>Local Access Point</b> field.</p> <p>From the drop-down list, select a remote access point to be associated with the newly created local access point. If none exist or to create a new one, select <b>New</b>. Enter the corresponding <b>Access Point Name</b> and <b>Network Address</b> in the adjacent fields.</p> <p>You can enter an existing access point name after selecting the <b>New</b> option. This causes the existing information to be updated with the new parameters. You can change only the host name and port number.</p> <p>The remote access point will also be the authentication principal for the WTC connection for inbound requests. Optionally, you can create a user with the same access point ID in the default security realm to allow incoming calls. To do so, select <b>Yes</b> from the <b>Create User?</b> drop-down list. The password will be randomly generated using a temporary variable to avoid security issues.</p>
Reply Buffer Type	<p>This option is available only if the <b>Response Required?</b> field is selected.</p> <p>Select the type of buffer that the remote Tuxedo client will receive.</p>
Reply Buffer Subtype	<p>This option is available only when the <b>Response Required?</b> option is selected and the <b>Reply Buffer Type</b> value is <b>VIEW</b> or <b>VIEW32</b>.</p> <p>Enter the buffer subtype with which to associate the reply buffer.</p>
Response Required?	<p>Select this check box if this service is expected to send a response.</p> <p>The default status is that this option is selected.</p> <p>This option is cleared and the unavailable if the service type is <b>Messaging Service</b> and the response message type is <b>None</b>.</p>
Request Encoding	<p>Specify a character set encoding for requests in Tuxedo transports.</p>

Option	To create or edit...
Response Encoding	Specify a character set encoding for responses in Tuxedo transports.
Transformation Style	Select one of the following: <ul style="list-style-type: none"> <li>• <b>None</b> - (default) The order of fields may not be respected.</li> <li>• <b>Ordered</b> - The fields are presented with all their occurrences in the correct order.</li> <li>• <b>Ordered and Grouped</b> - If the fields are logically structured as records, the fields are ordered by occurrence and grouped by record.</li> </ul>

## WS Transport Configuration page (Business Services)

Use this page to configure transport settings for a proxy service using the WS transport protocol. For more information about the WS transport, see the [WS Transport User Guide](#).

Option	To create or edit...
Response Timeout	Enter the number of seconds to wait for a response.  Leaving this field blank indicates that there is no response timeout. The business service will wait for the duration of the sequence timeout configured in the RM policy.  If you enter a zero (0) value, there is no timeout; as such, it will never time out.
Service Account	Enter a service account or click <b>Browse</b> to select one from the list displayed.  The service account specifies the credentials to use when there is an HTTP basic authentication policy on this service.
<b>Advanced Settings</b>	
Queue Error Messages	Select the check box to enable sending error messages to the configured error queue.

Option	To create or edit...
Error Queue URI	<p>This option is available only when the <b>Queue Error Messages</b> check box is selected.</p> <p>Enter the URI of JMS queue for storing error messages, in the following format:</p> <pre>jms://host:port/connFactoryJndiName/queueJndiName</pre>
JMS Error Queue Service Account	<p>This option is available only when the <b>Queue Error Messages</b> check box is selected.</p> <p>Enter a service account or click <b>Browse</b> to select one from the list displayed.</p> <p>The service account specifies the credentials to use for JNDI lookups and sending error messages to the error queue.</p>
Use SSL for Error Queue	<p>This option is available only when the <b>Queue Error Messages</b> check box is selected.</p> <p>Select the check box to use SSL for connecting to the error queue.</p>

## WS Transport Configuration page (Proxy Services)

Use this page to configure transport settings for a proxy service using the WS transport protocol. For more information about the WS transport, see the [WS Transport User Guide](#).

Option	To create or edit...
Dispatch Policy	<p>Select a dispatch policy for this endpoint or use the default dispatch policy.</p> <p>Dispatch policy refers to the instance of WLS Work Manager that you want to use for the service endpoint. For information about Work Managers, see <a href="#">Using Work Managers to Optimize Scheduled Work</a> and <a href="#">Create Work Manager</a> in the <i>WebLogic Server Administration Console Online Help</i>.</p>

### Advanced Settings

<b>Option</b>	<b>To create or edit...</b>
Retry Count	The number of times to retry delivery of a message to the pipeline. If an unhandled exception occurs in the request pipeline of a proxy service, the incoming WS transport message will be redelivered to the pipeline up to the number of times specified by the retry count. This value is important for reliably processing WS transport messages.
Retry Delay	The number of seconds the system pauses before retrying to send a message to the pipeline after an error.

## Transport Configuration