

SeeBeyond™ eBusiness Integration Suite

e*Way Intelligent Adapter for MQSeries User's Guide

Release 4.5.2

Monk Version



The information contained in this document is subject to change and is updated periodically to reflect changes to the applicable software. Although every effort has been made to ensure the accuracy of this document, SeeBeyond Technology Corporation (SeeBeyond) assumes no responsibility for any errors that may appear herein. The software described in this document is furnished under a License Agreement and may be used or copied only in accordance with the terms of such License Agreement. Printing, copying, or reproducing this document in any fashion is prohibited except in accordance with the License Agreement. The contents of this document are designated as being confidential and proprietary; are considered to be trade secrets of SeeBeyond; and may be used only in accordance with the License Agreement, as protected and enforceable by law. SeeBeyond assumes no responsibility for the use or reliability of its software on platforms that are not supported by SeeBeyond.

e*Gate, e*Insight, e*Way, e*Xchange, e*Xpressway, eBI, iBridge, Intelligent Bridge, IQ, SeeBeyond, and the SeeBeyond logo are trademarks and service marks of SeeBeyond Technology Corporation. All other brands or product names are trademarks of their respective companies.

© 1999–2001 by SeeBeyond Technology Corporation. All Rights Reserved. This work is protected as an unpublished work under the copyright laws.

This work is confidential and proprietary information of SeeBeyond and must be maintained in strict confidence.

Version 20011221160819.

Contents

Chapter 1

Introduction	6
Overview	6
Intelligent Queues and IQ Managers	6
Intended Reader	7
Components	7
Supported Operating Systems	7
System Requirements	7
External System Requirements	8

Chapter 2

Installation	9
Windows NT and Windows 2000	9
Pre-installation	9
Installation Procedure	9
UNIX	10
Pre-installation	10
Installation Procedure	10
AIX Systems	11
Files/Directories Created by the Installation	11

Chapter 3

Configuration	13
e*Way Configuration Parameters	13
General Settings	13
Journal File Name	13
Max Resends Per Message	14
Max Failed Messages	14
Forward External Errors	14
Communication Setup	15
Start Exchange Data Schedule	15
Stop Exchange Data Schedule	15
Exchange Data Interval	16

Down Timeout	16
Up Timeout	16
Resend Timeout	17
Zero Wait Between Successful Exchanges	17
Monk Configuration	17
Operational Details	19
How to Specify Function Names or File Names	25
Additional Path	26
Auxiliary Library Directories	26
Monk Environment Initialization File	27
Startup Function	27
Process Outgoing Message Function	28
Exchange Data with External Function	28
External Connection Establishment Function	29
External Connection Verification Function	30
External Connection Shutdown Function	30
Positive Acknowledgment Function	31
Negative Acknowledgment Function	31
Shutdown Command Notification Function	32
MQ Settings	32
Local MQ Install	33
Qmanager	33
Queue Name	33
MQ Get Buffer Length	34
Enable Connection Test	34
Connection Test Queue Name	34
Environment Configuration	34
External Configuration Requirements	35

Chapter 4

Implementation	36
Implementation Notes	36
Error Handling	37
Sample Configuration	37

Chapter 5

MQSeries e*Way Functions	38
Basic Functions	38
MQSeries e*Way External Init Functions	42
MQSeries Monk Functions	49
MQSeries Auxiliary Functions	57
MQSeries Structures	68

Contents

Structure Related Functions 72

Index 74

Introduction

This chapter introduces you to SeeBeyond™ Technology Corporation's (SeeBeyond™) e*Way Intelligent Adapter for the MQSeries. It includes an overview of this manual, and a list of system requirements for installation.

1.1 Overview

The MQSeries e*Way enables the e*Gate system to exchange data with an IBM MQSeries Application, Versions 5.0 and 5.1. The IBM MQSeries is “middleware” that provides commercial messaging and queuing services. Messaging enables programs to communicate with each other via messages instead of direct connection. Placing these messages in queues for temporary storage frees up programs to continue to work independently. This process also allows communication across a network of unlike components, processors, operating systems, and protocols.

1.1.1 Intelligent Queues and IQ Managers

A key component within e*Gate is the Intelligent Queue, which provides storage for data while inside the e*Gate system. Data from Event Types are inserted and retrieved when the Control Broker invokes an e*Way. The IQ Manager controls the different IQs. The MQSeries e*Way allows e*Gate to seamlessly exchange data with applications that are MQSeries enabled.

The MQSeries IQ allows e*Gate to leverage existing MQSeries operational and management infrastructure for its underlying persistent storage. The MQSeries IQ makes use of queuing capability, but does not make use of MQSeries channels.

Queuing allows applications to run independently of one another, at different speeds and times. Applications can send messages to a queue and get messages from a queue at any time.

The MQSeries e*Way is configurable and transparently integrates existing systems and databases to the MQSeries, through e*Gate. This document explains how to install and configure the MQSeries e*Way.

1.1.2 Intended Reader

The reader of this guide is presumed to be a developer or system administrator with responsibility for maintaining the e*Gate system; to have a high level of experience with Windows and UNIX operations and administration; to be thoroughly familiar with IBM's MQSeries and with Windows-style GUI operations.

1.1.3 Components

The MQSeries e*Way comprises the following:

- **stcewgenericmonk.exe**, the executable component
- Configuration files, which the e*Way Editor uses to define configuration parameters
- Monk functions (discussed in [Chapter 5](#))
- Dynamic Link Library (DLL) files

A complete list of installed files appears in [Table 1 on page 12](#).

1.2 Supported Operating Systems

The MQSeries e*Way is available on the following operating systems:

- Windows 2000, Windows 2000 SP1, and Windows 2000 SP2
- Windows NT 4.0 SP6a
- Solaris 2.6, 7, and 8
- AIX 4.3.3
- HP-UX 11 and HP-UX 11i
- Japanese Windows 2000, Windows 2000 SP1 , and Windows 2000 SP2
- Japanese Windows NT 4.0 SP6a
- Japanese Solaris 2.6, 7, and 8
- Japanese HP-UX 11.0

1.3 System Requirements

To use the MQSeries e*Way, you need the following:

- An e*Gate Participating Host, version 4.5 or later. For AIX operating systems, you need an e*Gate Participating Host, version 4.5.1 or later.
- A TCP/IP network connection.

- Additional disk space for e*Way executable, configuration, library, and script files. The disk space is required on both the Participating and the Registry Host. Additional disk space is required to process and queue the data that this e*Way processes; the amount necessary varies based on the type and size of the data being processed, and any external applications performing the processing.

1.4 External System Requirements

IBM MQSeries version 5.0 or 5.1.

For AIX systems, MQSeries requires a patch, available from IBM at:

<ftp://ftp.software.ibm.com/software/mqseries/fixes/aix51>

The README.TXT file contains information to help you determine which patches are applicable to your specific system.

It is recommended that AIX users install the **U471218.tar.Z** patch, if it has not already been applied.

Installation

This chapter explains how to install the MQSeries e*Way.

2.1 Windows NT and Windows 2000

2.1.1 Pre-installation

- 1 Exit all Windows programs before running the setup program, including any anti-virus applications.
- 2 You must have Administrator privileges to install this e*Way.

2.1.2 Installation Procedure

To install the MQSeries e*Way on a Windows system:

- 1 Log in as an Administrator to the workstation on which you want to install the e*Way.
- 2 Insert the e*Way installation CD-ROM into the CD-ROM drive.
- 3 If the CD-ROM drive's Autorun feature is enabled, the setup application should launch automatically; skip ahead to step 4. Otherwise, use the Windows Explorer or the Control Panel's **Add/Remove Applications** feature to launch the file **setup.exe** on the CD-ROM drive.
- 4 The InstallShield setup application launches. Follow the on-screen instructions to install the e*Way.

Note: *Be sure to install the e*Way files in the suggested **client** installation directory. The installation utility detects and suggests the appropriate installation directory. Unless you are directed to do so by SeeBeyond support personnel, do not change the suggested installation directory setting.*

- 5 After the installation is complete, exit the install utility and launch the Enterprise Manager.
- 6 In the Component editor, create a new e*Way.
- 7 Display the new e*Way's properties.

- 8 On the General tab, under **Executable File**, click **Find**.
- 9 Select the file **stcewgenericmonk.exe**.
- 10 Click **OK** to close the properties sheet, or continue to configure the e*Way. Configuration parameters are discussed in **Chapter 3**.

Note: *Once you have installed and configured this e*Way, you must incorporate it into a schema by defining and associating the appropriate Collaborations, Collaboration Rules, IQs, and Event Types before this e*Way can perform its intended functions. For more information about any of these procedures, please see the online Help system.*

*For more information about configuring e*Ways or how to use the e*Way Editor, see the e*Gate Integrator User's Guide.*

2.2 UNIX

2.2.1 Pre-installation

You do not require root privileges to install this e*Way. Log in under the user name that you wish to own the e*Way files. Be sure that this user has sufficient privilege to create files in the e*Gate directory tree.

2.2.2 Installation Procedure

To install the MQSeries e*Way on a UNIX system:

- 1 Log in on the workstation containing the CD-ROM drive, and insert the CD-ROM into the drive.
- 2 If necessary, mount the CD-ROM drive.
- 3 At the shell prompt, type:
cd /cdrom/setup
- 4 Start the installation script by typing:
setup.sh
- 5 A menu of options will appear. Select the **Install e*Way** option. Then, follow any additional on-screen directions.

Note: *Be sure to install the e*Way files in the suggested **client** installation directory. The installation utility detects and suggests the appropriate installation directory. Unless you are directed to do so by SeeBeyond support personnel, do not change the suggested installation directory setting.*

- 6 After installation is complete, exit the installation utility and launch the Enterprise Manager.

- 7 In the Component editor, create a new e*Way.
- 8 Display the new e*Way's properties.
- 9 On the **General** tab, under **Executable File**, click **Find**.
- 10 Select the file **stcewgenericmonk**.
- 11 Click **OK** to close the properties sheet, or continue to configure the e*Way. Configuration parameters are discussed in **Chapter 3**.

Note: *Once you have installed and configured this e*Way, you must incorporate it into a schema by defining and associating the appropriate Collaborations, Collaboration Rules, Intelligent Queues (IQs), and Event Types before this e*Way can perform its intended functions. For more information about any of these procedures, please see the online Help system.*

*For more information about configuring e*Ways or how to use the e*Way Editor, see the e*Gate Integrator User's Guide.*

2.2.3 AIX Systems

For AIX systems, MQSeries requires a patch, available from IBM at:

<ftp://ftp.software.ibm.com/software/mqseries/fixes/aix51/U471218>.

There are three files at that location:

- IY17668.tar.Z
- U471218.tar.Z
- README.TXT

The README.TXT file contains information that will help you determine which of the two patches are applicable to your specific system.

It is recommended that AIX users install the **U471218.tar.Z** patch, if it has not already been applied.

2.3 Files/Directories Created by the Installation

The MQSeries e*Way installation process will install the files shown in Table 1 below within the e*Gate **client** directory tree. Files will be installed within the **egate\client** tree on the Participating Host and committed to the **default** schema on the Registry Host.

Table 1 Files Created by the Installation

Install Directory	Files
bin\	stcewgenericmonk.exe stc_monkmqclient.dll stc_monkmqserver.dll
configs\stcewgenericmonk\	stcewmq.def
monk_library\MQ\	MQclient.monk MQserver.monk mq-stdver-eway-funcs.monk

Select the appropriate **.dll** file based on whether the installed MQSeries e*Way will be in server or client mode. The same applies to selecting the appropriate ***.monk** file to use. All other files displayed apply to both client and server modes.

Caution: *The **monk_MQclient.dll** and **monk_MQserver.dll** files cannot be run simultaneously by the same executable file. Trying to do so will cause run-time conflicts.*

Configuration

This chapter provides instructions for configuring the MQSeries e*Way.

3.1 e*Way Configuration Parameters

e*Way configuration parameters are set, using the e*Way Editor.

To change e*Way configuration parameters:

- 1 In the Enterprise Manager's Component editor, select the e*Way you want to configure and display its properties.
- 2 Under **Configuration File**, click **New** to create a new file, **Find** to select an existing configuration file, or **Edit** to edit the currently selected file.
- 3 In the **Additional Command Line Arguments** box, type any additional command line arguments that the e*Way may require, taking care to insert them *at the end* of the existing command-line string. Be careful not to change any of the default arguments unless you have a specific need to do so.

For more information about how to use the e*Way Editor, see the e*Way Editor's online Help or the *e*Gate Integrator User's Guide*.

The e*Way's configuration parameters are organized into the following sections:

- General Settings
- Communication Setup
- Monk Configuration
- MQ Settings

3.1.1 General Settings

The General Settings control basic operational parameters.

Journal File Name

Description

Specifies the name of the journal file.

Required Values

A valid file name, optionally including an absolute path (for example, **c:\temp\filename.txt**). If an absolute path is not specified, the file will be stored in the e*Gate **SystemData** directory. See the *e*Gate Integrator System Administration and Operations Guide* for more information about file locations.

Additional Information

An Event (package of data) will be journaled for the following conditions:

- When the number of resends is exceeded (see **Max Resends Per Message** below)
- When its receipt is due to an external error, but Forward External Errors is set to **No**. (See [“Forward External Errors” on page 14](#) for more information.)

Max Resends Per Message

Description

Specifies the number of times the e*Way will attempt to resend an Event to the external system after receiving an error.

Required Values

An integer between 1 and 1,024. The default is 5.

Max Failed Messages

Description

Specifies the maximum number of failed Events (messages) that the e*Way will allow. When the specified number of failed messages is reached, the e*Way will shut down and exit.

Required Values

An integer between 1 and 1,024. The default is 3.

Forward External Errors

Description

Selects whether error messages that begin with the string “DATAERR” that are received from the external system will be queued to the e*Way’s configured queue. See [“Exchange Data with External Function” on page 28](#) for more information.

Required Values

Yes or **No**. The default value, **No**, specifies that error messages will not be forwarded.

See [“Schedule-driven Data Exchange Functions” on page 22](#) for information about how the e*Way uses this function.

3.1.2 Communication Setup

The Communication Setup parameters control the schedule by which the e*Way obtains data from the external system.

Note: *The schedule you set using the e*Way's properties in the Enterprise Manager controls when the e*Way executable will run. The schedule you set within the parameters discussed in this section (using the e*Way Editor) determines when data will be exchanged. Be sure you set the **exchange data** schedule to fall within the **run the executable** schedule.*

Start Exchange Data Schedule

Description

Establishes the schedule to invoke the e*Way's **Exchange Data with External** function.

Required Values

One of the following:

- One or more specific dates/times
- A single repeating interval (such as yearly, weekly, monthly, daily, or every *n* seconds).

Also Required - If you set a schedule using this parameter, you must also define all three of the following functions:

- **Exchange Data With External**
- **Positive Acknowledgment**
- **Negative Acknowledgment**

If you do not do so, the e*Way will terminate execution when the schedule attempts to start.

Additional Information

When the schedule starts, the e*Way determines whether it is waiting to send an **ACK** or **NAK** to the external system (using the Positive and Negative Acknowledgment functions) and whether the connection to the external system is active. If no **ACK/NAK** is pending and the connection is active, the e*Way immediately executes the **Exchange Data with External** function. Thereafter, the **Exchange Data with External** function will be called according to the **Exchange Data Interval** parameter until the **Stop Exchange Data Schedule** time is reached.

See ["Exchange Data with External Function" on page 28](#), ["Exchange Data Interval" on page 16](#), and ["Stop Exchange Data Schedule" on page 15](#) for more information.

Stop Exchange Data Schedule

Description

Establishes the schedule to stop data exchange.

Required Values

One of the following:

- One or more specific dates/times
- A single repeating interval (such as yearly, weekly, monthly, daily, or every n seconds).

Exchange Data Interval

Description

Specifies the number of seconds the e*Way waits between calls to the **Exchange Data with External** function during scheduled data exchanges.

Required Values

An integer between 0 and 86,400. The default is 120.

Additional Information

If **Zero Wait Between Successful Exchanges** is set to **Yes** and the **Exchange Data with External Function** returns data, The **Exchange Data Interval** setting will be ignored and the e*Way will invoke the **Exchange Data with External Function** immediately.

If this parameter is set to zero, there will be no exchange data schedule set and the **Exchange Data with External Function** will never be called.

See [“Down Timeout” on page 16](#) and [“Stop Exchange Data Schedule” on page 15](#) for more information about the data-exchange schedule.

Down Timeout

Description

Specifies the number of seconds that the e*Way will wait between calls to the **External Connection Establishment** function. See [“External Connection Establishment Function” on page 29](#) for more information.

Required Values

An integer between 1 and 86,400. The default is 15.

Up Timeout

Description

Specifies the number of seconds the e*Way will wait between calls to the **External Connection Verification** function. See [“External Connection Verification Function” on page 30](#) for more information.

Required Values

An integer between 1 and 86,400. The default is 15.

Resend Timeout

Description

Specifies the number of seconds the e*Way will wait between attempts to resend an Event (message) to the external system, after receiving an error message from the external system.

Required Values

An integer between 1 and 86,400. The default is 10.

Zero Wait Between Successful Exchanges

Description

Selects whether to initiate data exchange after the **Exchange Data Interval** or immediately after a successful previous exchange.

Required Values

Yes or **No**. If this parameter is set to **Yes**, the e*Way will immediately invoke the **Exchange Data with External** function if the previous exchange function returned data. If this parameter is set to **No**, the e*Way will always wait the number of seconds specified by **Exchange Data Interval** between invocations of the **Exchange Data with External** function. The default is **No**.


See [“Exchange Data with External Function” on page 28](#) for more information.

3.1.3 Monk Configuration

The parameters in this section help you set up the information required by the e*Way to utilize Monk for communication with the external system.

Conceptually, an e*Way is divided into two halves. One half of the e*Way (shown on the left in [Figure 1 on page 18](#)) handles communication with the external system; the other half manages the Collaborations that process data and subscribe or publish to other e*Gate components.

Figure 1 e*Way Internal Architecture



The communications side of the e*Way uses Monk functions to start and stop scheduled operations, exchange data with the external system, package data as e*Gate Events and send those Events to Collaborations, and manage the connection between the e*Way and the external system. The **Monk Configuration** options discussed in this section control the Monk environment and define the Monk functions used to perform these basic e*Way operations. You may create and modify these functions using the SeeBeyond Collaboration Rules Editor or a text editor (such as **Notepad** or **UNIX vi**).

The communications side of the e*Way is single-threaded. Functions run serially, and only one function can be executed at a time. The business logic side of the e*Way is multi-threaded, with one executable thread for each Collaboration. Each thread maintains its own Monk environment; therefore, information such as variables, functions, path information, and so on cannot be shared between threads.

Operational Details

The Monk functions in the communications side of the e*Way fall into the following groups:


Type of Operation	Name
Initialization	Startup Function on page 27 (also see Monk Environment Initialization File on page 27)
Connection	External Connection Establishment Function on page 29 External Connection Verification Function on page 30 External Connection Shutdown Function on page 30
Schedule-driven data exchange	Exchange Data with External Function on page 28 Positive Acknowledgment Function on page 31 Negative Acknowledgment Function on page 31
Shutdown	Shutdown Command Notification Function on page 32
Event-driven data exchange	Process Outgoing Message Function on page 28

A series of figures on the next several pages illustrates the interaction and operation of these functions.

Initialization Functions

Figure 2 below illustrates how the e*Way executes its initialization functions.


Figure 2 Initialization Functions



Connection Functions

Figure 3 below illustrates how the e*Way executes the connection establishment and verification functions.

Figure 3 Connection Establishment and Verification Functions




Note: The e*Way selects the connection function based on an internal *up/down* flag rather than a poll to the external system. See [Figure 5 on page 23](#) and [Figure 7 on page 25](#) for examples of how different functions use this flag.

User functions can manually set this flag using Monk functions. See [send-external-up](#) on page 42 and [send-external-down](#) on page 41 for more information.

Figure 4 below illustrates how the e*Way executes its connection shutdown function.

Figure 4 Connection Shutdown Function



Schedule-driven Data Exchange Functions


Figure 5 on page 23 illustrates how the e*Way performs schedule-driven data exchange using the **Exchange Data with External Function**. The **Positive Acknowledgement Function** and **Negative Acknowledgement Function** are also called during this process.

“Start” can occur in any of the following ways:

- The **Start Data Exchange** time occurs
- Periodically during data-exchange schedule (after **Start Data Exchange** time, but before **Stop Data Exchange** time), as set by the Exchange Data Interval
- The **start-schedule** Monk function is called

After the function exits, the e*Way waits for the next start schedule time or command.


Figure 5 Schedule-driven Data Exchange Functions



Shutdown Functions

Figure 6 below illustrates how the e*Way implements the shutdown request function.

Figure 6 Shutdown Functions




Event-driven Data Exchange Functions

Figure 7 on page 25 illustrates event-driven data-exchange using the **Process Outgoing Message Function**.

Every two minutes, the e*Way checks the **Failed Message** counter against the value specified by the **Max Failed Messages** parameter. When the **Failed Message** counter exceeds the specified maximum value, the e*Way logs an error and shuts down.

After the function exits, the e*Way waits for the next outgoing Event.

Figure 7 Event-driven Data-exchange Functions



How to Specify Function Names or File Names

Parameters that require the name of a Monk function will accept either a function name or a file name. If you specify a file name, be sure that the file has one of the following extensions:

- *.monk
- *.tsc
- *.dsc

Additional Path

Description

Specifies a path to be appended to the load path, the path Monk uses to locate files and data (set internally within Monk). The directory specified in **Additional Path** will be searched after the default load paths.

Required Values

A path name, or a series of paths separated by semicolons. This parameter is optional and may be left blank.

Additional Information

The default load paths are determined by the **bin** and **Shared Data** settings in the ***.egate.store file**. See the *e*Gate Integrator System Administration and Operations Guide* for more information about this file.

To specify multiple directories, manually enter the directory names rather than selecting them with the **File Selection** button. Directory names must be separated with semicolons, and you can mix absolute paths with relative e*Gate paths. For example,

```
monk_scripts\my_dir;c:\my_directory
```

The internal e*Way function that loads this path information is called only once, when the e*Way first starts up.

Auxiliary Library Directories

Description

Specifies a path to auxiliary library directories. Any ***.monk** files found within those directories will automatically be loaded into the e*Way's Monk environment. This parameter is optional and may be left blank.

Required Values

A path name, or a series of paths separated by semicolons.

Additional Information

To specify multiple directories, manually enter the directory names rather than selecting them with the **File Selection** button. Directory names must be separated with semicolons, and you can mix absolute paths with relative e*Gate paths. For example,

```
monk_scripts\my_dir;c:\my_directory
```

The internal e*Way function that loads this path information is called only once, when the e*Way first starts up.

The default is **monk_library/MQ**.

This parameter is optional and may be left blank.

Monk Environment Initialization File

Specifies a file that contains environment initialization functions, which will be loaded after the auxiliary library directories are loaded. Use this feature to initialize the e*Way's Monk environment (for example, to define Monk variables that are used by the e*Way's function scripts).

Required Values

A file name within the load path, or file name plus path information (relative or absolute). If path information is specified, that path will be appended to the load path. See [“Additional Path” on page 26](#) for more information about the load path.

Additional information

Any environment-initialization functions called by this file accept no input, and must return a string. The e*Way will load this file and try to invoke a function of the same base name as the file name (for example, for a file named **my-init.monk**, the e*Way would attempt to execute the function **my-init**).

Typically, it is a good practice to initialize any global Monk variables that may be used by any other Monk Extension scripts.

The default is **MQ-stdver-init**.

The internal function that loads this file is called once when the e*Way first starts up (see [Figure 2 on page 20](#)).

Startup Function

Description

Specifies a Monk function that the e*Way will load and invoke upon startup or whenever the e*Way's configuration is reloaded. This function should be used to initialize the external system before data exchange starts.

Required Values

The name of a Monk function, or the name of a file (optionally including path information) containing a Monk function. This parameter is optional and may be left blank.

Additional Information

The function accepts no input, and must return a string.

The string **“FAILURE”** indicates that the function failed; any other string (including a null string) indicates success.

This function will be called after the e*Way loads the specified **Monk Environment Initialization** file and any files within the specified **Auxiliary Directories**.

The e*Way will load this file and try to invoke a function of the same base name as the file name (see [Figure 2 on page 20](#)). For example, for a file named **my-startup.monk**, the e*Way would attempt to execute the function **my-startup**.

The default is **MQ-stdver-startup**.

Process Outgoing Message Function

Description

Specifies the Monk function responsible for sending outgoing Events (messages) from the e*Way to the external system. This function is event-driven (unlike the Exchange Data with External function, which is schedule-driven).

Required Values

The name of a Monk function, or the name of a file (optionally including path information) containing a Monk function. *You may not leave this field blank.*

Additional Information

The function requires a non-null string as input (the outgoing Event to be sent) and must return a string.

The e*Way invokes this function when one of its Collaborations publishes an Event to an <EXTERNAL> destination (as specified within the Enterprise Manager). The function returns one of the following (see [Figure 7 on page 25](#) for more details):

- Null string - Indicates that the Event was published successfully to the external system.
- "RESEND" - Indicates that the Event should be resent.
- "CONNERR" - Indicates that there is a problem communicating with the external system.
- "DATAERR" - Indicates that there is a problem with the message (Event) data itself.
- If a string other than the following is returned, the e*Way will create an entry in the log file indicating that an attempt has been made to access an unsupported function.

Note: *If you wish to use **event-send-to-egate** to enqueue failed Events in a separate IQ, the e*Way must have an inbound Collaboration (with appropriate IQs) configured to process those Events.*

Exchange Data with External Function

Description

Specifies a Monk function that initiates the transmission of data from the external system to the e*Gate system and forwards that data as an inbound Event to one or more e*Gate Collaborations. This function is called according to a schedule (unlike the **Process Outgoing Message Function**, which is event-driven).

Required Values

The name of a Monk function, or the name of a file (optionally including path information) containing a Monk function. This parameter is optional and may be left blank.

Additional Information

The function accepts no input and must return a string (see [Figure 5 on page 23](#) for more details):

- Null string - Indicates that the data exchange was completed successfully. No information will be sent into the e*Gate system.
- "CONNERR" - Indicates that a problem with the connection to the external system has occurred.
- "DATAERR" - Indicates that a problem with the data itself has occurred. The e*Way handles the string "DATAERR" and "DATAERR" plus additional data differently; see [Figure 5 on page 23](#) for more details.
- Any other string - The contents of the string are packaged as an inbound Event. The e*Way must have at least one Collaboration configured suitably to process the inbound Event, as well as any required IQs.

The default is **MQ-stdver-data-exchg**.

This function is initially triggered by the **Start Data Exchange** schedule or manually by the Monk function **start-schedule**. After the function has returned true and the data received by this function has been acknowledged or not acknowledged (by the **Positive Acknowledgment Function** or **Negative Acknowledgment Function**, respectively), the e*Way checks the **Zero Wait Between Successful Exchanges** parameter.

If this parameter is set to **Yes**, the e*Way will immediately call the **Exchange Data with External** function again; otherwise, the e*Way will not call the function until the next scheduled **start exchange** time or the schedule is manually invoked using the Monk function **start-schedule** (see [start-schedule](#) on page 44 for more information).

External Connection Establishment Function

Description

Specifies a Monk function that the e*Way will call when it has determined that the connection to the external system is down.

Required Values

The name of a Monk function, or the name of a file (optionally including path information) containing a Monk function. *This field cannot be left blank.*

Additional Information

The function accepts no input and must return a string:

- "SUCCESS" or "UP" - Indicates that the connection was established successfully.
- Any other string (including the null string) - Indicates that the attempt to establish the connection failed.

This function is executed according to the interval specified within the **Down Timeout** parameter, and is *only* called according to this schedule.

The default is **MQ-stdver-conn-estab**.

The **External Connection Verification** function (see below) is called when the e*Way has determined that its connection to the external system is up.

External Connection Verification Function

Description

Specifies a Monk function that the e*Way will call when its internal variables show that the connection to the external system is up.

Required Values

The name of a Monk function. This function is optional; if no **External Connection Verification** function is specified, the e*Way will execute the **External Connection Establishment** function in its place.

Additional Information

The function accepts no input and must return a string:

- "SUCCESS" or "UP" - Indicates that the connection was established successfully.
- Any other string (including the null string) - Indicates that the attempt to establish the connection failed.

This function is executed according to the interval specified within the **Up Timeout** parameter, and is *only* called according to this schedule.

The default is **MQ-stdver-conn-ver**.

The **External Connection Establishment** function (see above) is called when the e*Way has determined that its connection to the external system is down.

External Connection Shutdown Function

Description

Specifies a Monk function that the e*Way will call to shut down the connection to the external system.

Required Values

The name of a Monk function. This parameter is optional.

Additional Information

This function requires a string as input, and may return a string.

This function will only be invoked when the e*Way receives a **suspend** command from a Control Broker. When the **suspend** command is received, the e*Way will invoke this function, passing the string "SUSPEND_NOTIFICATION" as an argument.

Any return value indicates that the "suspend" command can proceed and that the connection to the external system can be broken immediately.

The default is **MQ-stdver-conn-shutdown**.

Positive Acknowledgment Function

Description

Specifies a Monk function that the e*Way will call when *all* the Collaborations to which the e*Way sent data have processed and enqueued that data successfully.

Required Values

The name of a Monk function, or the name of a file (optionally including path information) containing a Monk function. This parameter is required if the **Exchange Data with External** function is defined.

Additional Information

The function requires a non-null string as input (the Event to be sent to the external system) and must return a string:

- “CONNERR” - Indicates a problem with the connection to the external system. When the connection is re-established, the **Positive Acknowledgment** function will be called again, with the same input data.
- Null string - The function completed execution successfully.

After the **Exchange Data with External** function returns a string that is transformed into an inbound Event, the Event is handed off to one or more Collaborations for further processing. If the Event’s processing is completed successfully by *all* the Collaborations to which it was sent, the e*Way executes the **Positive Acknowledgment** function (otherwise, the e*Way executes the **Negative Acknowledgment** function).

The default is **MQ-stdver-pos-ack**.

Negative Acknowledgment Function

Description

Specifies a Monk function that the e*Way will call when the e*Way fails to process and queue Events from the external system.

Required Values

The name of a Monk function, or the name of a file (optionally including path information) containing a Monk function. This parameter is required if the **Exchange Data with External** function is defined.

Additional Information

The function requires a non-null string as input (the Event to be sent to the external system) and must return a string:

- “CONNERR” - Indicates a problem with the connection to the external system. When the connection is re-established, the function will be called again.
- Null string - The function completed execution successfully.

This function is only called during the processing of inbound Events. After the **Exchange Data with External** function returns a string that is transformed into an inbound Event, the Event is handed off to one or more Collaborations for further processing. If the Event’s processing is not completed successfully by *all* the

Collaborations to which it was sent, the e*Way executes the **Negative Acknowledgment** function (otherwise, the e*Way executes the **Positive Acknowledgment** function).

The default is **MQ-stdver-neg-ack**.

Shutdown Command Notification Function

Description

Specifies a Monk function that will be called when the e*Way receives a **shut down** command from the Control Broker. This parameter is optional.

Required Values

The name of a Monk function.

Additional Information

When the Control Broker issues a shutdown command to the e*Way, the e*Way will call this function with the string "SHUTDOWN_NOTIFICATION" passed as a parameter.

The function accepts a string as input and must return a string:

- A null string or "SUCCESS" - Indicates that the shutdown can occur immediately.
- Any other string - Indicates that shutdown must be postponed. Once postponed, shutdown will not proceed until the Monk function **shutdown-request** is executed (see [shutdown-request](#) on page 43).

The default is **MQ-stdver-shutdown**.

Note: *If you postpone a shutdown using this function, be sure to use the (**shutdown-request**) function to complete the process in a timely manner.*

3.1.4 MQ Settings

The MQ Settings section enables you to configure the parameters that support queuing and the connection to the IBM MQSeries. A message queue is a named destination to which messages can be sent. A message is a string of bytes that has meaning to the applications that use the message. MQSeries messages consist of two parts, a message descriptor and application data. The content and structure of the application data are defined by the application programs that use them. The message descriptor identifies the message and contains other control information or attributes, such as data, the time the message was created, type of message, and the priority assigned to the message.

Messages accumulate on queues until they are retrieved by programs that service those queues. A queue can be either a buffer area in the memory of a computer or a data set on a permanent storage device such as a disk.

Before an application can send messages, a queue manager and some queues must be created. Queues reside in, and are managed by, a queue manager. Queue managers have the responsibility for monitoring that

- Attributes are changed according to commands received.
- Events, such as trigger events are generated when the appropriate conditions are met.
- Messages are put into the correct queue, as requested by the application, or routed to another queue manager. When this cannot be accomplished, the application is informed and an appropriate error message code is provided.

Applications access queues only through the external services of the queue manager. These applications can open a queue, put messages on it, get messages from it, and close the queue.

Local MQ Install

Description

Use this setting to configure the e*Way as either client or server. If the MQSeries server software was installed on the host running this e*Way, set this parameter to **server**. If the MQSeries client software was installed on the host running this e*Way, set this parameter to **client**.

Required Values

The type of installation, either **client** or **server**. The default is **server**.

Additional Information

None.

Qmanager

Description

Specifies the name of the IBM MQSeries queue manager.

Required Values

A queue manager's name.

Additional Information

None.

Queue Name

Description

Specifies the MQSeries message queue name.

Required Values

A queue name.

Additional Information

None.

MQ Get Buffer Length

Description

Specifies the maximum size of the MQSeries receive buffer.

Required Values

An integer between 1,024 and 4,194,304. The default is 8192.

Additional Information

None.

Enable Connection Test

Description

Specifies whether or not the e*Way should attempt a connection to the Connection Test Queue at a regular interval to verify the connection is still alive.

Required Values

When set to **enable**, the e*Way will attempt the connection. If set to **disable**, no connection attempt will be made.

Additional Information

None.

Connection Test Queue Name

Description

Specifies the name of the MQSeries Connection Test Queue.

Required Values

A name that identifies the Test Queue Connection.

Additional Information

None.

3.2 Environment Configuration

To support the operation of this e*Way, no changes are necessary

- In the Participating Host's operating environment
- In the e*Gate system

Note: *Changes to Monk files can be made using the Collaboration Rules Editor (available from within the Enterprise Manager) or with a text editor. However, if you use a text editor to edit Monk files directly, you **must** commit these changed files to the e*Gate Registry or your changes will not be implemented.*

*For more information about committing files to the e*Gate Registry, see the Enterprise Manager's online Help system, or the **stcregutil** command-line utility in the e*Gate Integrator System Administration and Operations Guide.*

3.3 External Configuration Requirements

There are no configuration changes required in the external system. All necessary configuration changes can be made within e*Gate.

Implementation

This chapter includes information on implementing the MQSeries e*Way.

4.1 Implementation Notes

Follow these steps to use the MQSeries e*Way:

- 1 Install the software required in this order. Follow the procedures for installing e*Gate as outlined in the e*Gate Integrator Installation Guide.
- 2 Install the MQSeries e*Way from the **Add-Ons** folder on the CD.
- 3 Check to ensure the MQ Manager is up and running. Refer to the *MQ Quick Start Guide* (supplied by IBM) for instructions.
- 4 Ensure the MQ Administrator creates a queue for the MQ Manager that will be used.
- 5 Configure the MQSeries e*Way, as explained in [Chapter 3](#).
- 6 Make sure you have the **MQCONN** stored in your start-up file connection establishment function (see [MQCONN](#) on page 64).
- 7 If you are working with only one MQ Manager, the MQ-connect function will be issued only once. However, if you're working with multiple MQ Managers, put this function in the start-up file so you can issue it as needed.
- 8 Select the MQSeries functions you will use and configure them (see ["MQSeries e*Way External Init Functions"](#) on page 46)
- 9 Open a queue using the **MQOPEN** function (see [MQOPEN](#) on page 68).
- 10 Perform an **MQGET** function (see [MQGET](#) on page 67) or an **MQPUT** function (see [MQPUT](#) on page 69). This will be determined by whether or not you want to read from the queue (**get**) or write to the queue (**put**).
- 11 Add an option to close to your finished script.
- 12 Disconnect from the MQ Manager.

4.2 Error Handling

The MQ *.dll file checks the execution status of its underlying MQ API functions. In case of a failed operation, this file reports the error code and the reason for the failed call via its internal string variables **MQ-errno** and **MQ-error**.

MQ-errno contains the numeric value associated with the failed call (similar to **errno** for C-library calls). And **MQ-error** is the verbose explanation for the failure.

All the Monk functions in the *.dll file have been created to return a Boolean false (**#f**), if the call to an underlying MQ API function that fails. In such cases, examine the contents of **MQ-errno** and **MQ-error** to see what caused the failure.

There are 230 error codes (called reason codes in MQ). Look up these codes in the MQSeries online documentation in the following section:

MQSeries Application Programming Reference, Chapter 5, "Return Codes"

You can take action, as determined by the nature of the error.

Note: *The MQSeries e*Way displays a warning if it receives a message that is larger than the configured message size.*

4.3 Sample Configuration

A sample configuration is available in the **samples** directory of the e*Gate CD-ROM. Navigate to the following directory:

samples/ewmq

MQSeries e*Way Functions

The MQSeries e*Way's functions fall into the following categories:

- [Basic Functions](#) on page 38
- [MQSeries e*Way External Init Functions](#) on page 42
- [MQSeries Monk Functions](#) on page 49
- [MQSeries Auxiliary Functions](#) on page 57

Note: The functions described in this section can only be used by the functions defined within the e*Way's configuration file. None of the functions are available to Collaboration Rules scripts executed by the e*Way.

5.1 Basic Functions

The functions in this category control the e*Way's most basic operations.

The basic functions are

- [event-send-to-egate](#) on page 38
- [get-logical-name](#) on page 39
- [send-external-down](#) on page 39
- [send-external-up](#) on page 40
- [shutdown-request](#) on page 40
- [start-schedule](#) on page 41
- [stop-schedule](#) on page 41

event-send-to-egate

Syntax

(event-send-to-egate *string*)

Description

event-send-to-egate sends data that the e*Way has already received from the external system into the e*Gate system as an Event.

Parameters

Name	Type	Description
string	String	The data to be sent to the e*Gate system.

Return Values

Boolean

Returns true (**#t**) if the data is sent successfully; otherwise, returns false (**#f**).

Throws

None.

Additional information

This function can be called by any e*Way function when it is necessary to send data to the e*Gate system in a blocking fashion.

get-logical-name

Syntax

```
(get-logical-name)
```

Description

get-logical-name returns the logical name of the e*Way.

Parameters

None.

Return Values

string

Returns the name of the e*Way (as defined by the Enterprise Manager).

Throws

None.

send-external-down

Syntax

```
(send-external-down)
```

Description

send-external down instructs the e*Way that the connection to the external system is down.

Parameters

None.

Return Values

None.

Throws

None.

send-external-up

Syntax

```
(send-external-up)
```

Description

send-external-up instructs the e*Way that the connection to the external system is up.

Parameters

None.

Return Values

None.

Throws

None.

shutdown-request

Syntax

```
(shutdown-request)
```

Description

shutdown request requests the e*Way to perform the shutdown procedure when there is no outstanding incoming/outgoing event. When the e*Way is ready to act on the shutdown request, it invokes the Shutdown Command Notification Function (see "[Shutdown Command Notification Function](#)" on page 32). Once this function is called, the shutdown proceeds immediately.

Once interrupted, the e*Way's shutdown cannot proceed until this Monk function is called. If you do interrupt an e*Way shutdown, we recommend that you complete the process in a timely fashion.

Parameters

None.

Return Values

None.

Throws

None.

start-schedule

Syntax

```
(start-schedule)
```

Description

start-schedule requests that the e*Way execute the **Exchange Events with External** function specified within the e*Way's configuration file. Does not effect any defined schedules.

Parameters

None.

Return Values

None.

Throws

None.

stop-schedule

Syntax

```
(stop-schedule)
```

Description

stop-schedule requests that the e*Way halt execution of the **Exchange Events with External** function specified within the e*Way's configuration file. Execution will be stopped when the e*Way concludes any open transaction. Does not effect any defined schedules, and does not halt the e*Way process itself.

Parameters

None.

Return Values

None.

Throws

None.

5.2 MQSeries e*Way External Init Functions

Access these functions from the `monk_library\Mq\mq-stdver-eway-funcs.monk`. They provide entry points into the `*.def` file. The following are examples of default functions for the e*Way's configuration:

- [MQ-stdver-conn-estab](#) on page 42
- [MQ-stdver-conn-shutdown](#) on page 42
- [MQ-stdver-conn-ver](#) on page 43
- [MQ-stdver-data-exchg](#) on page 43
- [MQ-stdver-data-exchg-stub](#) on page 44
- [MQ-stdver-init](#) on page 45
- [MQ-stdver-neg-ack](#) on page 45
- [MQ-stdver-pos-ack](#) on page 46
- [MQ-stdver-proc-outgoing](#) on page 47
- [MQ-stdver-proc-outgoing-stub](#) on page 47
- [MQ-stdver-shutdown](#) on page 48
- [MQ-stdver-startup](#) on page 45

MQ-stdver-conn-estab

Syntax

(MQ-stdver-conn-estab)

Description

MQ-stdver-conn-estab is used to connect to the external system. This function expects no input.

Parameters

None.

Return Values

This function must return **up** or **success** when the connection is established. Any other return indicates the connection was not established.

Throws

None.

MQ-stdver-conn-shutdown

Syntax

(MQ-stdver-conn-shutdown *string*)

Description

MQ-stdver-conn-shutdown is called by the e*Gate system to request that the interface disconnect from the external system, when e*Gate is preparing for a suspend/reload cycle.

Parameters

Name	Type	Description
string	String	When the e*Way calls this function, e*Gate will pass the string "SUSPEND_NOTIFICATION" as the parameter.

Return Values

string

Any return indicates that the suspend can occur immediately, which puts the e*Way into a **down** state. The user can choose to define the return string as **success**, **#t** (true) or simply a null string.

Throws

None.

MQ-stdver-conn-ver

Syntax

(MQ-stdver-conn-ver)

Description

MQ-stdver-conn-ver is used to verify the connection with the external system. This function expects no input.

Parameters

None.

Return Values

This function must return **up** or **success** when the connection is established. Any other return indicates the connection was not established.

Throws

None.

MQ-stdver-data-exchg

Syntax

(MQ-stdver-data-exchg)

Description

MQ-stdver-data-exchg is used to send a message received from the external system to e*Gate. This function expects no input.

Parameters

None.

Return Values

string

This function returns a null string, indicating a successful operation; nothing is sent to e*Gate.

When a **<message-string>** is returned, an Event is sent to e*Gate.

<CONNERR> is used if the connection to the external system was lost, and sets the system state to **down**.

Throws

None.

MQ-stdver-data-exchg-stub

Syntax

```
(MQ-stdver-data-exchg-stub)
```

Description

MQ-stdver-data-exchg-stub is used as a place holder for the function entry point for sending a message received from the external system to e*Gate, when the interface is configured as an outbound only connection. This function is used to catch configuration problems. The function expects no input.

Parameters

None.

Return Values

string

This function returns a null string, indicating a successful operation; nothing is sent to e*Gate.

When a **<message-string>** is returned, an Event is sent to e*Gate.

<CONNERR> is used if the connection to the external system was lost, and sets the system state to **down**.

Throws

None.

MQ-stdver-init

Syntax

(MQ-stdver-init)

Description

MQ-stdver-init allows you to post Events into the e*Gate system from within a Monk function. This function expects no input.

Parameters

None.

Return Values

string

<FAILURE> causes shutdown of the e*Way. Any other return indicates success.

Throws

None.

MQ-stdver-startup

Syntax

(MQ-stdver-startup)

Description

MQ-stdver-startup is used for instance specific function loads and environment setup. This function does not expect input.

Parameters

None.

Return Values

string

<FAILURE> causes shutdown of the e*Way. Any other return indicates success.

Throws

None.

MQ-stdver-neg-ack

Syntax

(MQ-stdver-neg-ack)

Description

MQ-stdver-neg-ack is used to send a negative acknowledgment to the external system, as well as for post processing after failing to send data to e*Gate. This function expects input in the form of data sent to e*Gate.

Parameters

None.

Return Values

string

This function returns a null string, indicating a successful operation.

<CONNERR> indicates a loss of connection with the external. This puts the e*Way into a down state. The e*Way will attempt to connect and upon successful reconnection, the **Negative Acknowledgement** function will be re-executed.

Throws

None.

MQ-stdver-pos-ack

Syntax

```
(MQ-stdver-pos-ack)
```

Description

MQ-stdver-pos-ack is used to send a positive acknowledgment to the external system, as well as for post processing after successfully sending data to e*Gate. This function expects input in the form of data sent to e*Gate.

Parameters

None.

Return Values

string

This function returns null string, indicating a successful operation.

<CONNERR> indicates a loss of connection with the external. This puts the e*Way into a **down** state. The e*Way will attempt to connect and upon successful reconnection the **Positive Acknowledgement** function will be re-executed.

Throws

None.

MQ-stdver-proc-outgoing

Syntax

(MQ-stdver-proc-outgoing)

Description

MQ-stdver-proc-outgoing is used to send an Event from e*Gate to the external system. This function expects an Event sent from e*Gate as the input.

Parameters

None.

Return Values

string

This function returns a null string, indicating a successful operation.

<RESEND> causes the Event to be immediately resent.

<CONNERR> indicates a loss of connection with the external. This puts the e*Way into a down state. The e*Way will attempt to connect and upon successful reconnection, this function will be re-executed with the same input Event.

<DATAERR> is used if the function experiences problems processing the data. If the function is journaled enabled, the input Event is journaled and the failed Event count is increased.

Throws

None.

Additional Information

Use the **event-send-to-egate** function to place any bad Events into a bad-Event queue.

MQ-stdver-proc-outgoing-stub

Syntax

(MQ-stdver-proc-outgoing-stub)

Description

MQ-stdver-proc-outgoing-stub is used as a place holder for the function entry point for sending an Event received from e*Gate to the external system, when the interface is configured as an inbound-only connection. This function is used to catch configuration problems. This function expects an Event sent from e*Gate as the input.

Parameters

None.

Return Values

string

This function returns a null string, indicating a successful operation.

<RESEND> causes the Event to be immediately resent.

<CONNERR> indicates a loss of connection with the external. This puts the e*Way into a down state. The e*Way will attempt to connect and upon successful reconnection, this function will be re-executed with the same input Event.

<DATAERR> is used if the function experiences problems processing the data. If the function is journaled enabled, the input Event is journaled and the failed Event count is increased.

Throws

None.

Notes

Use the **event-send-to-egate** function to place any bad Events into a bad-Event queue.

MQ-stdver-shutdown

Syntax

(MQ-stdver-shutdown *string*)

Description

MQ-stdver-shutdown is called by the e*Gate system to request that the e*way disconnect from the external system, in preparation for a suspend/reload cycle.

Parameters

Name	Type	Description
string	String	When the e*Way calls this function, e*Gate will pass the string "SHUTDOWN_NOTIFICATION" as the parameter.

Return Values

Any return value indicates that the suspend can occur immediately, which puts the e*Way into a down state.

Throws

None.

5.3 MQSeries Monk Functions

To better understand how the following functions are used, a discussion of the Message Queue Interface (MQI) is needed. The MQI comprises the following items:

- Calls (APIs) through which applications can access the queue manager.
- Structures that applications use to pass data to, and get data from the queue manager.
- Elementary data types for passing data to, and getting data from the queue manager.

The MQSeries Monk functions are

[MQBACK](#) on page 49

[MQBEGIN](#) on page 50

[MQCLOSE](#) on page 50

[MQCMIT](#) on page 51

[MQCONN](#) on page 52

[MQCONNX](#) on page 52

[MQDISC](#) on page 53

[MQGET](#) on page 53

[MQOPEN](#) on page 54

[MQPUT](#) on page 55

[MQPUT1](#) on page 56

MQBACK

Syntax

(MQBACK *conn-handle*)

Description

MQBACK tells the queue manager to back out of the queue all messages put on the queue or retrieved from the queue as part of a single unit of work.

Parameters

Name	Type	Description
conn-handle	Connection handle	A connection handle.

Return Values

Boolean

Returns **#t** (true) if successful; otherwise, returns **#f** (false).

Throws

None.

Example

```
(define hConn (MQCONN "Sample_QM"))
(define bool-ret (MQBACK hConn))
)
```

MQBEGIN

Syntax

```
(MQBEGIN conn-handle mqbo-ptr)
```

Description

MQBEGIN starts a unit of work only when MQSeries is acting as a XA transaction coordinator. In all other cases, the start transaction is implicit in **MQCONN**, **MQBACK**, or **MQCMIT**.

Parameters

Name	Type	Description
conn-handle	Connection handle	A connection handle.
mqbo-ptr	String	The definition of the MQBO data structure.

Return Values

Boolean

Returns **#t** (true) if successful; otherwise, returns **#f** (false).

Throws

None.

Example

```
(define hConn (MQCONN "Sample_QM"))
(define mqbo-ptr (init-MQBO-struct))
(define bool-ret (MQBEGIN hConn mqbo-ptr))
```

MQCLOSE

Syntax

```
(MQCLOSE conn-hdl obj-hdl option)
```

Description

MQCLOSE closes the queue.

Parameters

Name	Type	Description
conn-hdl	Connection handle	A connection handle.
obj-hdl	Object handle	The object handle.
option	String	The action performed by MQCLOSE .

Return Values

Boolean

Returns **#t** (true) if successful; otherwise, returns **#f** (false).

Throws

None.

Examples

```
(define hConn (MQCONN "Sample_QM"))
(define mqod-ptr (init-MQOD-struct))
(define open-option (MQ-create-config-value `#("MQOO_INPUT_SHARED"
"MQOO_OUTPUT" "MQOO_FAIL_IF QUIESCING")))
(define hObj (MQOPEN hConn mqod-ptr open-option))
(define bool-ret (MQCLOSE hConn hObj 0))
```

MQCMIT

Syntax

```
(MQCMIT conn-handle)
```

Description

MQCMIT commits all changes made to the queue.

Parameters

Name	Type	Description
conn-handle	Connection handle	A connection handle.

Return Values

Boolean

Returns **#t** (true) if successful; otherwise, returns **#f** (false).

Throws

None.

Examples

```
(define hConn (MQCONN "Sample_QM"))
(define bool-ret (MQCMIT hConn))
```

MQCONN

Syntax

```
(MQCONN queue manager name)
```

Description

MQCONN provides a connection to the queue manager.

Parameters

Name	Type	Description
queue manager name	String	The name of the queue manager.

Return Values

string

Returns a connection handle if successful; otherwise, returns **#f** (false).

Throws

None.

Examples

```
(define hConn (MQCONN "Sample_QM")) where hConn is the connection handle)
```

MQCONNX

Syntax

```
(MQCONNX queue-manager-name mqcno-ptr)
```

Description

MQCONNX connects the application to the queue manager.

Parameters

Name	Type	Description
queue-manager-name	String	The name of the queue manager.
mqcno-ptr	String	The definition of the MQCNO data structure.

Return Values

Boolean

Returns **#t** (true) if successful; otherwise, returns **#f** (false).

Throws

None.

Examples

```
(define mqcno-ptr (init-MQCNO-struct))
(define hConn (MQCONNX "Sample_QM" mqcno-ptr))
```

Note: *MQCONNX is identical in functionality to MQCONN, but provides the additional parameter for specifying the MQCNO data structure.*

MQDISC

Syntax

```
(MQDISC conn-hdl)
```

Description

MQDISC disconnects the application from the queue manager.

Parameters

Name	Type	Description
conn-hdl	Connection handle	The connection handle.

Return Values

Boolean

Returns **#t** (true) if successful; otherwise, returns **#f** (false).

Throws

None.

Examples

```
(define mqcno-ptr (init-MQCNO-struct))
(define hConn (MQCONNX "Sample_QM" mqcno-ptr))
(define bool-ret (MQDISC hConn))
)
```

MQGET

Syntax

```
(MQGET conn-hdl obj-hdl mqmd-ptr mqgmo-ptr buffer-length)
```

Description

MQGET retrieves the Event.

Parameters

Name	Type	Description
conn-hdl	Connection handle	The connection handle.
obj-hdl	Object handle	The object handle.

Name	Type	Description
mqmd-ptr	String	The definition of the MQMD data structure.
mqgmo-ptr	String	The definition of the MQGMO data structure.
buffer-length	Integer	The length in bytes of the buffer.

Return Values

string

Returns a message string if successful, otherwise, returns **#f** (false).

Throws

None.

Examples

```
(define mqcno-ptr (init-MQCNO-struct))
(define hConn (MQCONNX "Sample_QM" mqcno-ptr))
(define mqod-ptr (init-MQOD-struct))
(define open-option (MQ-create-config-value `#("MQOO_INPUT_SHARED"
"MQOO_OUTPUT" "MQOO_FAIL_IF QUIESCING")))
(define hObj (MQOPEN hConn mqod-ptr open-option))
(define mqmd-ptr (init-MQMD-struct))
(define mqgmo-ptr (init-MQGMO-struct))
(define message (MQGET hConn hObj mqmd-ptr mqgmo-ptr 1024))
```

MQOPEN

Syntax

```
(MQOPEN conn-handle mqod-ptr option)
```

Description

MQOPEN opens a message queue.

Parameters

Name	Type	Description
conn-handle	Connection handle	A connection handle.
mqod-ptr	String	The definition of the MQOD data structure.
option	String	The action performed by MQOPEN .

Return Values

string

Returns an object handle if successful; otherwise, returns **#f** (false).

Throws

None.

Examples

```
((define hConn (MQCONN "Sample_QM"))
(define mqod-ptr (init-MQOD-struct))
(define open-option (MQ-create-config-value `#("MQOO_INPUT_SHARED"
"MQOO_OUTPUT" "MQOO_FAIL_IF QUIESCING")))
(define hObj (MQOPEN hConn mqod-ptr open-option)))
```

MQPUT

Syntax

```
(MQPUT conn-hdl obj-hdl mqmd-ptr mqpmo-ptr buffer)
```

Description

MQPUT puts the Event in the queue.

Parameters

Name	Type	Description
conn-hdl	Connection handle	The connection handle.
obj-hdl	Object handle	The object handle
mqmd-ptr	String	The definition of the MQMD data structure.
mqpmo-ptr	String	The definition of the MQPMO data structure.
buffer	String	The data contained in the Event.

Return Values

Boolean

Returns **#t** (true) if successful; otherwise, returns **#f** (false).

Throws

None.

Examples

```
(define mqcno-ptr (init-MQCNO-struct))
(define hConn (MQCONN "Sample_QM" mqcno-ptr))
(define mqod-ptr (init-MQOD-struct))
(define open-option (MQ-create-config-value `#("MQOO_INPUT_SHARED"
"MQOO_OUTPUT" "MQOO_FAIL_IF QUIESCING")))
(define hObj (MQOPEN hConn mqod-ptr open-option))
(define mqmd-ptr (init-MQMD-struct))
(define mqpmo-ptr (init-MQPMO-struct))
(define message (MQPUT hConn hObj mqmd-ptr mqpmo-ptr "my testing
message"))
```

MQPUT1

Syntax

```
(MQPUT1 conn-hdl mqod-ptr mqmd-ptr mqpmo-ptr buffer)
```

Description

MQPUT1 puts the Event in the queue.

Parameters

Name	Type	Description
conn-hdl	Connection handle	The connection handle.
mqod-ptr	String	The definition of the MQOD data structure.
mqmd-ptr	String	The definition of the MQMD data structure.
mqpmo-ptr	String	The definition of the MQPMO data structure.
buffer	String	The data contained in the Event.

Return Values

Boolean

Returns **#t** (true) if successful; otherwise, returns **#f** (false).

Throws

None.

Examples

```
(define mqcno-ptr (init-MQCNO-struct))
(define hConn (MQCONN "Sample_QM" mqcno-ptr))
(define mqod-ptr (init-MQOD-struct))
(define mqmd-ptr (init-MQMD-struct))
(define mqpmo-ptr (init-MQPMO-struct))
(define message (MQPUT1 hConn mqod-ptr mqmd-ptr mqpmo-ptr "my testing
message"))
```


5.4 MQSeries Auxiliary Functions

The functions explained in this section rely on the information presented under “[MQSeries Structures](#)” on page 68. The structure names and their field names must be used as input arguments when using these auxiliary functions and must be an exact match of the table entries. The data types for the individual fields specify how they are used in Monk.

The MQSeries Auxiliary Functions are

- [MQ-check-type](#) on page 57
- [MQ-configure-close-options](#) on page 58
- [MQ-configure-get-options](#) on page 58
- [MQ-configure-open-options](#) on page 60
- [MQ-configure-options](#) on page 61
- [MQ-configure-put-options](#) on page 62
- [MQ-create-config-value](#) on page 63
- [MQ-get-field](#) on page 64
- [MQ-init-type](#) on page 65
- [MQ-reset-type](#) on page 65
- [MQ-set-field](#) on page 66

MQ-check-type

Syntax

`(MQ-check-type MQtype MQobject)`

Description

MQ-check-type checks to see if the **MQobject** is of type **MQtype**.

Parameters

Name	Type	Description
MQtype	String	The string containing the name of an MQ data structure.
MQobject	String	A Monk object used to represent type MQtype .

Return Values

Boolean

Returns **#t** (true) if **MQobject** is of type **MQtype**; otherwise, returns **#f** (false).

Throws

None.

Examples

```
(define Object_Descriptor (MQ-init-type "MQOD"))
(define result (MQ-check-type "MQOD" Object_Descriptor))
```

Note: This function fails if any mismatches appear between the input arguments to this function.

MQ-configure-close-options

Parameter Name	Description
MQCO_NONE	An option that tells the queue manager no optional close processing is required. This must be specified for <ul style="list-style-type: none"> ▪ Objects other than queues ▪ Predefined queues ▪ Temporary dynamic queues (but only in those cases where Hobj is not the handle returned by the MQOPEN call that created the queue) ▪ Distribution lists In all of the above cases, the object is retained and not deleted.
MQCO_DELETE	An option that tells the queue manager to delete the queue. The queue is deleted if either of the following is true: <ul style="list-style-type: none"> ▪ It is a permanent dynamic queue, and there are no Events on the queue and no uncommitted get or put requests outstanding for the queue (either for the current task or any other task). ▪ It is the temporary dynamic queue that was created by the MQOPEN call that returned Hobj. In this case, all the Events on the queue are purged.
MQCO_DELETE_PURGE	An option that tells the queue manager to delete the queue, purging any messages. The queue is deleted if either of the following is true: <ul style="list-style-type: none"> ▪ It is a permanent dynamic queue and there are no uncommitted get or put requests outstanding for the queue (either for the current task or any other task). ▪ It is the temporary dynamic queue that was created by the MQOPEN call that returned Hobj.

MQ-configure-get-options

Parameter Name	Description
MQGMO_NONE	An option used when no options are specified.

Parameter Name	Description (Continued)
MQGMO_NO_WAIT	An option that tells the queue manager to return immediately when no acceptable Events are available. This is the opposite of the MQGMO_WAIT option, and is defined to aid program documentation. This is the default if neither option is specified.
MQGMO_WAIT	An option that tells the queue manager to wait for an acceptable Event to arrive. The maximum time for waiting is specified in the WaitInterval parameter.
MQGMO_SYNCPOINT	An option that tells the queue manager to get the Event using syncpoint control. The request is to operate within the normal unit of work protocols. This marks the Event as unavailable to other applications, but it is deleted from the queue only when the unit of work is committed. The Event is made available again after the unit of work is backed out.
MQGMO_NO_SYNCPOINT	An option that tells the queue manager to get the Event without using syncpoint control. The request is to operate within the normal unit of work protocols. The Event is deleted from the queue immediately (unless this is a browse request). The Event can not be made available again by backing out a unit of work.
MQGMO_SET_SIGNAL	An option that requests a signal is to be set. This option is used in conjunction with the Signal1 and Signal2 fields to allow applications to proceed with other work while waiting for an Event to arrive, and also (if suitable operating system facilities are available) to wait for Events arriving on more than one queue.
MQGMO_BROWSE_FIRST	An option that tells the queue manager to browse from the beginning of the queue.
MQGMO_BROWSE_NEXT	An option that tells the queue manager to browse from its current position on the queue. The browse cursor is advanced to the next message on the queue that satisfies the selection criteria specified on the MQGET call. The message is returned to the application, but remains on the queue.
MQGMO_ACCEPT_TRUNCATED_MSG	An option that allows truncation of Event data. If the Event buffer is insufficient to hold the complete Event, this option allows the MQGET call to fill the buffer with as much of the Event as the buffer can hold, issue a warning completion code, and complete its processing.
MQGMO_MARK_SKIP_BACKOUT	An option that allows a unit of work to be backed out from the queue, without reinstating the Event marked with this option.
MQGMO_MSG_UNDER_CURSOR	An option that causes the Event pointed to by the browse cursor to be retrieved, regardless of the MQMO_* options specified in the MatchOptions field in MQGMO . The message is removed from the queue.

Parameter Name	Description (Continued)
MQGMO_LOCK	An option that locks the Event being browsed, to prevent the Event from being visible to any other handle open for the queue. The option can be specified only if one of the following options is also specified: <ul style="list-style-type: none"> ▪ MQGMO_BROWSE_FIRST ▪ MQGMO_BROWSE_NEXT ▪ MQGMO_BROWSE_MSG_UNDER_CURSOR
MQGMO_UNLOCK	An option that unlocks the Event. The Event must have been previously locked by an MQGET call with the MQGMO_LOCK option.
MQGMO_BROWSE_MSG_UNDER_CURSOR	An option that causes the Event pointed to by the browser cursor to be retrieved nondestructively, regardless of the MQMO_* options specified in the MatchOptions field in MQGMO .
MQGMO_SYNCPOINT_IF_PERSISTENT	An option that tells the queue manager to get the Event using syncpoint control if the Event is persistent. A persistent Event has the value MQPER_PERSISTENT in the Persistence field in MQMD .
MQGMO_FAIL_IF_QUIESCING	An option that tells the queue manager to fail when it is in a quiet state.
MQGMO_CONVERT	An option that requests that the application data in the message be converted, to conform to the CodedCharSetId and Encoding values specified in the MsgDesc parameter on the MQGET call, before the data is copied to the buffer parameter.
MQGMO_LOGICAL_ORDER	An option that controls the order in which Events are returned by successive MQGET calls for the queue handle. The option must be specified on each of those calls in order to have an effect.
MQGMO_COMPLETE_MSG	An option that specifies that only a complete logical Event can be returned by the MQGET call.
MQGMO_ALL_MSGS_AVAILABLE	An option that specifies that Events in a group become available for retrieval only when all Events in the group are available.
MQGMO_ALL_SEGMENTS_AVAILABLE	An option that specifies that segments in a logical Event become available for retrieval only when all segments in the logical Event are available.

MQ-configure-open-options

Parameter Name	Description
MQOO_INPUT_AS_Q_DEF	An open queue used to get Events using the queue-defined default.
MQOO_INPUT_SHARED	An open queue used to get Events with shared access.

Parameter Name	Description
MQOO_INPUT_EXCLUSIVE	An open queue used to get Events with exclusive access.
MQOO_BROWSE	An open queue used to browse messages. The queue is opened for use with subsequent MQGET calls with one of the following options: <ul style="list-style-type: none"> ▪ MQGMO_BROWSE_FIRST ▪ MQGMO_BROWSE_NEXT ▪ MQGMO_BROWSE_MSG_UNDER_CURSOR
MQOO_OUTPUT	An open queue to put Events into.
MQOO_SAVE_ALL_CONTEXT	A Save context used when an Event is retrieved. Context information is associated with this queue handle.
MQOO_PASS_IDENTITY_CONTEXT	An option which allows MQPMO_PASS_IDENTITY_CONTEXT option to be specified in the PutMsgOpts parameter, which allows all identity context to be passed when an Event is put on a queue.
MQOO_PASS_ALL_CONTEXT	An option which allows MQPMO_PASS_ALL_CONTEXT option to be specified in the PutMsgOpts parameter, which allows all context to be passed when an Event is put on a queue.
MQOO_SET_IDENTITY_CONTEXT	An option which allows MQPMO_SET_IDENTITY_CONTEXT option to be specified in the PutMsgOpts parameter, which allows the identity context to be set when an Event is put on a queue.
MQOO_SET_ALL_CONTEXT	An option which allows the MQPMO_SET_ALL_CONTEXT option to be specified in the PutMsgOpts parameter, which allows all context to be set when an Event is put on a queue.
MQOO_ALTERNATE_USER_AUTHORITY	A method to validate that the AlternateUserId field in the ObjDesc parameter contains a user identifier.
MQOO_FAIL_IF_QUIESCING	An option that tells the queue manager to fail when it is in a quiet state (inactive).

MQ-configure-options

Syntax

(MQ-configure-options *options*)

Description

MQ-configure-options merges the long integer values in the passed-in vector into one long integer-option value.

Parameters

Name	Type	Description
options	Integer	The action of MQ-configure-options is controlled with this function.

Return Values

integer

Returns an option value consisting of a long integer.

Boolean

Returns **#f** (false) if unsuccessful.

Throws

None.

Examples

```
(define INPUT_SHARED 2)
(define OUTPUT 16)
(define FAIL_IF QUIESCING 8192)
(MQ-configure-options `#(INPUT_SHARED OUTPUT FAIL_IF QUIESCING))
```

MQ-configure-put-options

Parameter Name	Description
MQPMO_NONE	An option used when no options are specified.
MQPMO_SYNCPOINT	An option that tells the queue manager to put the Event into the queue using syncpoint control. The request is to operate within the normal unit of work protocols. The Event is not visible outside the unit of work until the unit of work is committed. If the unit of work is backed out, the Event is deleted.
MQPMO_NO_SYNCPOINT	An option that tells the queue manager to put the Event into the queue without using syncpoint control. The request is to operate outside the normal unit of work protocols. The Event is available immediately and can not be deleted by backing out a unit of work.
MQPMO_DEFAULT_CONTEXT	An option that tells the queue manager to use default context. An Event is to have default context information associated with it, for both identity and origin.
MQPMO_NEW_MSG_ID	An option that causes the queue manager to replace the contents of the MsgId field in MQMD with a new identifier.
MQPMO_NEW_CORREL_ID	An option that causes the queue manager to replace the contents of the CorrelId field in MQMD with a new identifier.

Parameter Name	Description
MQPMO_PASS_IDENTITY_CONTEXT	An option used to pass the identity context from an input queue handle.
MQPMO_PASS_ALL_CONTEXT	An option used to pass all context from an input queue handle.
MQPMO_SET_IDENTITY_CONTEXT	An option used to set identity context from the application.
MQPMO_SET_ALL_CONTEXT	An option used to set all context from the application.
MQPMO_ALTERNATE_USER_AUTHORITY	An option that tells the queue manager to validate the Event using a specified user identifier.
MQPMO_FAIL_IF QUIESCING	An option that tells the queue manager to fail if the queue manager is quiet (that is, an inactive state).
MQPMO_NO_CONTEXT	An option that tells the e*Way that no context is to be associated with the Event.
MQPMO_LOGICAL_ORDER	An option that tells the queue manager in what order the application will put Events in groups and segments of logical Events.

MQ-create-config-value

Syntax

(MQ-create-config-value *options*)

Description

MQ-create-config-value converts the strings in the input vector to integer equivalents in a vector of integers and passes that vector to the **MQ-configure-options** function.

Parameters

Name	Type	Description
options	String	A vector of strings to be converted to integers.

Return Values

integer

Returns an option value consisting of a long integer.

Throws

None.

Examples

```
(define MQ-create-config-value
  (lambda (values)
    (let ((options 0)(len 0))
      (set! len (vector-length values))
      (set! options (make-vector len 0))
      (do ((i 0 (+ i 1))) ((>= i len))
        (vector-set! options i (cadr (assoc (string->symbol (vector-ref
values i)) $MQ-ASSOCS$))))
      )
      (MQ-configure-options options)
    )))
```

Note: This function fails if a string that is not a part of the supported list is passed to it.

MQ-get-field

Syntax

```
(MQ-get-field MQtype field_name MQobject)
```

Description

MQ-get-field returns the value of the specified field in **MQobject**.

Parameters

Name	Type	Description
MQtype	String	The string containing the name of an MQ-data structure.
field_name	String	A Monk object used to represent type MQtype .
MQobject	String	A Monk object used to represent type MQtype .

Return Values

string

Returns the basic MQ-data-type of the field.

Throws

None.

Examples

```
(define MQGMO (MQ-init-type "mqgmo"))
(define GetOption (MQ-create-config-value `#("MQGMO_SYNCPOINT")))
(MQ-set-field "MQGMO" "Options" MQGMO GetOption)
(define value (MQ-get-field "MQGMO" "Options" MQGMO))
```

Note: This function fails if any mismatches appear between the input arguments to this function.

MQ-init-type

Syntax

```
(MQ-init-type MQtype )
```

Description

MQ-init-type creates the specified **MQobject** and initializes it with default values.

Parameters

Name	Type	Description
MQtype	String	The string containing the name of an MQ-data structure.

Return Values

string

Returns an **MQobject** of type string.

Throws

None.

Examples

```
(define Object_Descriptor (MQ-init-type "MQOD"))
```

Note: This function fails if the input argument to this function is not supported by the *monk_MQclient.dll* or *monk_MQserver.dll* files.

MQ-reset-type

Syntax

```
(MQ-reset-type MQtype MQobject)
```

Description

MQ-reset-type takes an **MQobject** of type **MQtype** and resets its contents to their default values.

Parameters

Name	Type	Description
MQtype	String	The string containing the name of an MQ-data structure.
MQobject	String	A Monk object used to represent type MQtype .

Return Values

Boolean

Returns **#t** (true) if **MQobject** is of type **MQtype**; otherwise, returns **#f** (false).

Throws

None.

Examples

```
(define Object_Descriptor (MQ-init-type "MQOD"))
...
(MQ-reset-type "MQOD" Object_Descriptor)
```

Note: This function fails if any mismatches appear between the input arguments to this function.

MQ-set-field

Syntax

```
(MQ-set-field MQtype field_name MQobject value)
```

Description

MQ-set-field takes an **MQobject** of type **MQtype** and sets the value of its internal field (as specified in **field_name**) to the given value.

Parameters

Name	Type	Description
MQtype	String	The string containing the name of an MQ-data structure.
field_name	String	A string containing the name of the member field in MQtype .
MQobject	String	A Monk object used to represent type MQtype .
value	String	The value assigned to field_name .

Return Values

Boolean

Returns **#t** (true) if successful; otherwise, returns **#f** (false).

Throws

None.

Examples

```
(define MQGMO (MQ-init-type "mqgmo"))
(define GetOption (MQ-create-config-value `#("MQGMO_SYNCPOINT")))
(MQ-set-field "MQGMO" "Options" MQGMO GetOption)
```

Note: *This function fails if any mismatches appear between the input arguments to this function.*

5.5 MQSeries Structures

The table, starting below, documents the MQ data structures that the MQ *.dll files allow you to modify. The first column contains the name of the structure, the second column shows a subset of the fields within that structure, which you can modify, and the third column shows the basic data types for the individual fields.

Structure	Field Name	Data Type
MQBO	Options Version	MQLONG MQLONG
MQCNO	Options Version	MQLONG MQLONG
MQDH	CodedCharSetId Encoding Flags Format ObjectRecOffset PutMsgRecFields PutMsgRecOffset RecsPresent StrucLength Version	MQLONG MQLONG MQLONG STRING MQLONG MQLONG MQLONG MQLONG MQLONG MQLONG
MQDLH	CodedCharSetId DestQMgrName DesQName Encoding Format PutAppName PutAppType PutDate PutTime Reason Version	MQLONG STRING STRING MQLONG STRING STRING STRING STRING STRING MQLONG MQLONG
MQGMO	GroupStatus MatchOptions Options Reserved1 ResolvedQName SegmentStatus Segmentation Signa11 Signa12 Version WaitInterval	MQCHAR MQLONG MQLONG MQCHAR STRING MQCHAR MQCHAR MQLONG MQLONG MQLONG MQLONG

Structure (Continued)	Field Name	Data Type
MQIHH	Authenticator	STRING
	CodedCharSetId	MQLONG
	CommitMode	MQCHAR
	Encoding	MQLONG
	Flags	MQLONG
	Format	STRING
	LTermOverride	STRING
	MFSMapName	STRING
	ReplyToFormat	STRING
	Reserved	MQCHAR
	SecurityScope	MQCHAR
	StrucLength	MQLONG
	TranInstancId	STRING
	TranState	MQCHAR
	Version	MQLONG
MQMD	AccountingToken	STRING
	ApplIdentityData	STRING
	ApplOriginData	STRING
	BackoutCount	MQLONG
	CodedCharSetId	MQLONG
	CorrelId	STRING
	Encoding	MQLONG
	Expiry	MQLONG
	Feedback	MQLONG
	Format	STRING
	GroupId	STRING
	MsgFlags	MQLONG
	MsgId	STRING
	MsgSeqNumber	MQLONG
	MsgType	MQLONG
	Offset	MQLONG
	OriginalLength	MQLONG
	Persistence	MQLONG
	Priority	MQLONG
	PutAppName	STRING
PutApplType	MQLONG	
PutDate	STRING	
PutTime	STRING	
ReplyToQ	STRING	
ReplyToQMgr	STRING	
Report	MQLONG	
UserIdentifier	STRING	
Version	MQLONG	

Structure (Continued)	Field Name	Data Type	
MQMD1	AccountingToken	STRING	
	ApplIdentityData	STRING	
MQMD1	ApplOriginData	STRING	
	BackoutCount	MQLONG	
	CodedCharSetId	MQLONG	
	CorrelId	STRING	
	Encoding	MQLONG	
	Expiry	MQLONG	
	Feedback	MQLONG	
	Format	STRING	
	MsgId	STRING	
	MsgType	MQLONG	
	Persistence	MQLONG	
	Priority	MQLONG	
	PutApplName	STRING	
	PutApplType	MQLONG	
	PutDate	STRING	
	PutTime	STRING	
	ReplyToQ	STRING	
	ReplyToQMgr	STRING	
	Report	MQLONG	
	UserIdentifier	STRING	
Version	MQLONG		
MQMDE	CodedCharSetId	MQLONG	
	Encoding	MQLONG	
	Flags	MQLONG	
	Format	STRING	
	GroupId	STRING	
	MsgFlags	MQLONG	
	MsgSeqNumber	MQLONG	
	Offset	MQLONG	
	OriginalLength	MQLONG	
	StrucLength	MQLONG	
	Version	MQLONG	
	MQOD	AlternateUsrId	STRING
		DynamicQName	STRING
InvalidDestCount		MQLONG	
KnownDestCount		MQLONG	
ObjectName		STRING	
ObjectQMgrName		STRING	
ObjectRecOffset		MQLONG	
ObjectType		MQLONG	
RecsPresent		MQLONG	
ResponseRecOffset		MQLONG	
UnknownDestCount		MQLONG	
Version		MQLONG	
MQOR		ObjectName	STRING
	ObjectQMgrName	STRING	

Structure (Continued)	Field Name	Data Type
MQPMO	Context InvalidDestCount KnownDestCount Options Put6MsgRecFields PutMsgRecOffset RecsPresent ResolvedQMgrName ResolvedQName ResponseRecOffset Timeout UnknownDestCount Version	MLONG MLONG MLONG MLONG MLONG MLONG MLONG STRING STRING MLONG MLONG MLONG MLONG
MQRMH	CodedCharSetId DataLogicalLength DataLogicalOffset DataLogicalOffset2 DestEnvLength DestEnvOffset DestNameLength DestNameOffset Encoding Flags Format ObjectInstanceId ObjectType SrcEnvLength SrcEnvOffset SrcNameLength SrcNameOffset StrucLength Version	MLONG MLONG MLONG MLONG MLONG MLONG MLONG MLONG MLONG MLONG STRING STRING STRING MLONG MLONG MLONG MLONG MLONG MLONG
MQRR	CompCode Reason	MLONG MLONG
MQTM	ApplId ApplType EnvData ProcessName QName TriggerData UsrData Version	STRING MLONG STRING STRING STRING STRING STRING MLONG

Structure (Continued)	Field Name	Data Type
MQTMC2	ApplId	STRING
	ApplType	STRING
	EnvData	STRING
	ProcessName	STRING
	QMgrName	STRING
	QName	STRING
	Trigger Data	STRING
	UsrData	STRING
	Version	STRING
MQXQH	MsgDesc	MQMD1
	RemoteQMgrName	STRING
	RemoteQName	STRING
	Version	MQLONG

5.6 Structure Related Functions

MQMD-struct-get-Contents

Syntax

(MQMD-struct-get-Contents *MQMDpointer*)

Description

MQMD-struct-get-Contents creates a binary image of all the fields in one action.

Parameters

Name	Type	Description
MQMDpointer	Opaque handle	Handle or pointer to the MQMD structure.

Return Values

blob

Returns the binary image of all fields.

Throws

None.

Additional Information

The MQMD structure is composed of several fields. In order to grab an image of the MQMD (and avoid doing multiple “gets” and “puts”) use the function **MQMD-struct-get-Contents**, which provides a binary image of all the fields in one action. The inverse function, **MQMD-struct-set-Contents** takes this binary image and superimposes it on the outgoing message. (These same functions exists for every supported MQ structure

that the .dll supports; XXX-struct-get-Contents or XXX-struct-set-Contents, substituting the structure name for XXX.)

MQMD-struct-set-Contents

Syntax

```
(MQMD-struct-set-contents MQMDpointer blob)
```

Description

MQMD-struct-set-Contents takes the binary image created by MQMD-struct-set-Contents and superimposes it on the outgoing message.

Parameters

Name	Type	Description
MQMDpointer	Opaque handle	Handle or pointer to the MQMD structure.
blob	Blob	The binary image that is being set.

Return Values

Boolean

Returns #t (true)

Throws

None.

Additional Information

The MQMD structure is composed of several fields. In order to grab an image of the MQMD (and avoid doing multiple “gets” and “puts”) use the function **MQMD-struct-get-Contents**, which provides a binary image of all the fields in one action. The inverse function, **MQMD-struct-set-Contents** takes this binary image and superimposes it on the outgoing message. (These same functions exists for every supported MQ structure that the .dll supports; XXX-struct-get-Contents or XXX-struct-set-Contents, substituting the structure name for XXX.)

Index

A

- Additional Path parameter 26
- AIX 8
 - patch 11
- Auxiliary Library Directories parameter 26

C

- components 7
- configuration parameters 13
 - Additional Path 26
 - Auxiliary Library Directories 26
 - Down Timeout 16
 - Exchange Data Interval 16
 - Exchange Data With External Function 28
 - External Connection Establishment Function 29
 - External Connection Shutdown Function 30
 - External Connection Verification Function 30
 - Forward External Errors 14
 - Journal File Name 13
 - Max Failed Messages 14
 - Max Resends Per Message 14
 - Monk Environment Initialization File 27
 - Negative Acknowledgment Function 31
 - Positive Acknowledgement Function 31
 - Process Outgoing Message Function 28
 - Resend Timeout 17
 - Shutdown Command Notification Function 32
 - Start Exchange Data Schedule 16
 - Startup Function 27
 - Stop Exchange Data Schedule 15
 - Up Timeout 16
 - Zero Wait Between Successful Exchanges 17
- connection test queue name 34

D

- Down Timeout parameter 16

E

- enable connection test 34
- error handling 37
- Exchange Data Interval parameter 16

- Exchange Data with External Function parameter 28
- External Connection Establishment Function parameter 29
- External Connection Shutdown Function parameter 30
- External Connection Verification Function parameter 30
- external system requirements 8

F

- Forward External Errors parameter 14
- Functions
 - get-logical-name 39
 - start-schedule 41
 - stop-schedule 41
- functions 56
 - MQBACK 49
 - MQBEGIN 50
 - MQ-check-type 57
 - MQCLOSE 50
 - MQCMIT 51
 - MQ-configure-close-options 58
 - MQ-configure-get-options 58
 - MQ-configure-open-options 60
 - MQ-configure-options 61
 - MQ-configure-put-options 62
 - MQCONN 52
 - MQCONNX 52
 - MQ-create-config-value 63
 - MQDISC 53
 - MQGET 53
 - MQ-get-field 64
 - MQ-init-type 65
 - MQOPEN 54
 - MQPUT 55
 - MQ-reset-type 65
 - MQSeries 49
 - MQSeries auxiliary 57
 - MQSeries structures 68
 - MQ-set-field 66
 - MQ-stdver-conn-estab 42
 - MQ-stdver-conn-shutdown 42
 - MQ-stdver-data-exchg 43
 - MQ-stdver-data-exchg-stub 44
 - MQ-stdver-init 45
 - MQ-stdver-neg-ack 45
 - MQ-stdver-pos-ack 46
 - MQ-stdver-proc-outgoing 47
 - MQ-stdver-proc-outgoing-stub 47
 - MQ-stdver-shutdown 48
 - MQ-stdver-startup 45

G

get-logical-name 39

I

implementation notes 36
 installation 9
 AIX 11
 Windows NT and Windows 2000 9
 installation procedure
 UNIX 10
 Windows NT and Windows 2000 9
 intended reader 7

J

Journal File Name parameter 13

L

local MQ install 33

M

Max Failed Messages parameter 14
 Max Resends Per Message parameter 14
 message queue 32
 Monk Environment Initialization File parameter 27
 MQ get buffer length 34
 MQ settings parameter 32
 MQBACK 49, 50
 MQBEGIN 50
 MQ-check-type 57
 MQCLOSE 50
 MQCMIT 51
 MQ-configure-close-options 58
 MQ-configure-get-options 58
 MQ-configure-open-options 60
 MQ-configure-options 61
 MQ-configure-put-options 62
 MQCONN 52
 MQCONNX 52
 MQ-create-config-value 63
 MQDISC 53
 MQGET 53
 MQ-get-field 64
 MQ-init-type 65
 MQOPEN 54
 MQPUT 55
 MQPUT1 56
 MQ-reset-type 65
 MQSeries auxiliary functions 57
 MQSeries DataGateWay

 set up 36
 MQSeries monk functions 49
 MQSeries structures 68
 MQ-set-field 66
 MQ-stdver-conn-estab 42
 MQ-stdver-conn-shutdown 42
 MQ-stdver-data-exchg 43
 MQ-stdver-data-exchg-stub 44
 MQ-stdver-init 45
 MQ-stdver-neg-ack 45
 MQ-stdver-pos-ack 46
 MQ-stdver-proc-outgoing 47
 MQ-stdver-proc-outgoing-stub 47
 MQ-stdver-shutdown 48
 MQ-stdver-startup 45

N

Negative Acknowledgment Function parameter 31

O

Overview 6

P

parameters
 connection test queue 34
 enable connection test 34
 local MQ install 33
 MQ get buffer length 34
 MQ settings 32
 queue manager name 33
 queue name 33
 Positive Acknowledgment Function parameter 31
 Process Outgoing Message Function parameter 28

Q

queue manager 33
 queue manager name 33
 queue name 33

R

Resend Timeout parameter 17

S

sample implementation 37
 Schedules 41
 Shutdown Command Notification Function
 parameter 32

Index

Start Exchange Data Schedule parameter 16
start-schedule 41
Startup Function parameter 27
stcewgenericmonk.exe 7
Stop Exchange Data Schedule parameter 15
stop-schedule 41
system requirements 7
 AIX 8
 external 8

U

UNIX
 installation 10
Up Timeout parameter 16

W

Windows NT and Windows 2000
 pre-installation 9

Z

Zero Wait Between Successful Exchanges parameter
17