



Sun™ MTP J3270 User's Guide

Release 7.2

Sun Microsystems, Inc.
901 San Antonio Road
Palo Alto, CA 94303-4900 U.S.A.
650-960-1300

Part No. 816-2798-10
November 2001, Revision A

Send comments about this document to: docfeedback@sun.com

Copyright © 2001 Sun Microsystems, Inc., 901 San Antonio Road, Palo Alto, California 94303, U.S.A. All rights reserved.

Sun Microsystems, Inc. has intellectual property rights relating to technology embodied in this product. In particular, and without limitation, these intellectual property rights may include one or more of the U.S. patents listed at <http://www.sun.com/patents> and one or more additional patents or pending patent applications in the U.S. and other countries.

This product or document is distributed under licenses restricting its use, copying distribution, and decompilation. No part of this product or document may be reproduced in any form by any means without prior written authorization of Sun and its licensors, if any.

Third-party software, including font technology, is copyrighted and licensed from Sun suppliers.

Parts of the product may be derived from Berkeley BSD systems, licensed from the University of California. UNIX is a registered trademark in the U.S. and in other countries, exclusively licensed through X/Open Company, Ltd.

Sun, Sun Microsystems, and the Sun logo are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries.

Federal Acquisitions: Commercial Software - Government Users Subject to Standard License Terms and Conditions.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

Copyright © 2001 Sun Microsystems, Inc., 901 San Antonio Road, Palo Alto, California 94303, Etats-Unis. Tous droits réservés.

Sun Microsystems, Inc. a les droits de propriété intellectuels relatants à la technologie incorporée dans ce produit. En particulier, et sans la limitation, ces droits de propriété intellectuels peuvent inclure un ou plus des brevets américains énumérés à <http://www.sun.com/patents> et un ou les brevets plus supplémentaires ou les applications de brevet en attente dans les Etats - Unis et les autres pays.

Ce produit ou document est protégé par un copyright et distribué avec des licences qui en restreignent l'utilisation, la copie, la distribution, et la décompilation. Aucune partie de ce produit ou document ne peut être reproduite sous aucune forme, par quelque moyen que ce soit, sans l'autorisation préalable et écrite de Sun et de ses bailleurs de licence, s'il y en a.

Le logiciel détenu par des tiers, et qui comprend la technologie relative aux polices de caractères, est protégé par un copyright et licencié par des fournisseurs de Sun.

Des parties de ce produit pourront être dérivées des systèmes Berkeley BSD licenciés par l'Université de Californie. UNIX est une marque déposée aux Etats-Unis et dans d'autres pays et licenciée exclusivement par X/Open Company, Ltd.

Sun, Sun Microsystems, et le logo Sun, sont des marques de fabrique ou des marques déposées de Sun Microsystems, Inc. aux Etats-Unis et dans d'autres pays.

LA DOCUMENTATION EST FOURNIE "EN L'ETAT" ET TOUTES AUTRES CONDITIONS, CONDITIONS, DECLARATIONS ET GARANTIES EXPRESSES OU TACITES SONT FORMELLEMENT EXCLUES, DANS LA MESURE AUTORISEE PAR LA LOI APPLICABLE, Y COMPRIS NOTAMMENT TOUTE GARANTIE IMPLICITE RELATIVE A LA QUALITE MARCHANDE, A L'APTITUDE A UNE UTILISATION PARTICULIERE OU A L'ABSENCE DE CONTREFAÇON.



Contents

Chapter 1	Introduction	
1.1	Typographic conventions	1-1
1.2	Notation conventions	1-2
Chapter 2	Installing MTP J3270	
2.1	Prerequisites	2-1
2.2	Installing MTP J3270	2-1
Chapter 3	Using MTP J3270	
3.1	Invoking MTP J3270	3-1
3.2	Command line parameters	3-1
3.3	3270 emulator window functions	3-3
3.4	Connecting to a 3270 system	3-4
3.5	Specifying keyboard mapping	3-5
3.6	Using MTP J3270 in DBCS mode	3-6
3.6.1	Available 3270 field types	3-6
3.6.1.1	Restrictions on a pure single-byte field	3-6
3.6.1.2	Restrictions on a pure double-byte field	3-6
3.6.1.3	Restrictions on mixed (SOSI) fields	3-6
3.7	Making an association with an Internet browser	3-7
	Index	

Figures

Figure 2.1	MTP J3270 Installation Destination Location Screen	2-2
Figure 2.2	MTP J3270 Start Menu Option	2-2
Figure 3.1	Disconnected Emulator	3-3
Figure 3.2	Emulator Connect Window	3-4

Tables

Table 1.1	Typographic Conventions	1-1
Table 1.2	Notation Conventions	1-2
Table 3.1	MTP J3270 Key Maps	3-5

This document describes how to install and use the MTP J3270. J3270 is a 3270 terminal emulator that provides support for 3278 models 2, 3, 4 and 5 in both extended and non-extended mode. MTP J3270 allows you to connect to any Telnet3270 Server, such as MTP running the **unikixtnemux** server.

This chapter lists text and command notation conventions and explains how to contact technical support.

[Chapter 2](#) explains how to install MTP J3270.

[Chapter 3](#) describes how to invoke and use MTP J3270.

1.1 Typographic conventions

[Table 1.1](#) lists the typographic conventions used in this document.

Table 1.1 Typographic Conventions

Description	Example
Pathnames, directories, file names and extensions are in italics.	<i>C:\j3270</i>
Commands, error messages and text user must enter are shown in bold.	j3270
User-defined items are shown as bold italicized characters.	<i>3278-3-E</i>
Indicates actions or situations that pose possible serious damage to equipment, data or software.	 Caution
Indicates actions or situations that pose a hazard to any person or irreversible damage to data or the operating system.	 Warning
Information that appears on screens, including field labels, is shown as Arial characters.	Terminal Type

1.2 Notation conventions

This format is used for commands

command required_argument [*optional_argument*]

Table 1.2 Notation Conventions

Notation	Description
[]	Square brackets indicate optional arguments.
{ }	Braces that contain information separated by a vertical bar represent alternative options, one of which must be present
	Vertical bars between arguments indicate to select only one of the arguments.
...	Ellipses indicate that the preceding argument may be repeated one or more times.

If a command does not support an *optional_argument*, enter the command and press Return.

MTP J3270 runs on Windows 95, Windows 98, Windows NT, and Windows 2000 systems.

2.1 Prerequisites

For each MTP region you wish to connect to with MTP J3270, you must configure the **unikixtnemux** server. Refer to the *Configuration Guide*.

2.2 Installing MTP J3270



MTP J3270 is shipped as an InstallShield executable on all MTP distribution media.

- After you install MTP on a UNIX system, the InstallShield executable is located in the `$UNIX/MTP_J3270` directory. If you wish to use MTP J3270, you must copy the executable to a Windows platform.
- On the Windows NT CD-ROM, the file is a stand-alone executable. Run this executable to begin the installation process.

The MTP J3270 InstallShield executable contains the Java Runtime Environment (JRE) and code necessary to MTP J3270. Run the installation executable and follow the on-screen prompts to uncompress the files to the hard drive.

Follow these steps to install MTP J3270.

Step #	Description
1	Start the installation by either double-clicking the <code>.exe</code> file, or on the Windows desktop, select Start -> Run Enter the name of the MTP J3270 executable and click OK.
2	When the Welcome screen appears, read it and click Next.
3	When the Software License Agreement screen appears, read it and if you agree to the conditions, click Yes to continue.
4	On the User Information screen, enter user and company names and click Next.

Step #	Description
5	<p>When the Choose Destination Location screen appears, select where you wish to install MTP J3270, and click Next.</p>  <p>Figure 2.1 MTP J3270 Installation Destination Location Screen</p>
6	<p>Follow the on-screen prompts to complete the installation.</p>
7	<p>When the installation is complete, you can start MTP J3270 from the Start Menu. You can use MTP J3270 without having to reboot your system.</p>  <p>Figure 2.2 MTP J3270 Start Menu Option</p>

Chapter 3 Using MTP J3270

3.1 Invoking MTP J3270

There are three ways to invoke MTP J3270.

From the Windows Start Menu	Select Start -> Programs -> Sun MTP J3270 -> 3270 Terminal
From a shortcut	You can set up a Windows shortcut to start the <i>j3270.exe</i> program.
From a command prompt	If you are in the MTP J3270 <i>bin</i> directory or if the MTP J3270 <i>bin</i> directory is in your path, type j3270

With all of these methods, you can specify startup parameters. You can modify the properties of the Start button entry for the 3270 Terminal or the properties of a shortcut you created. From a command prompt, specify the options on the command line. [Section 3.2](#) describes these parameters.

3.2 Command line parameters

You can invoke MTP J3270 with a series of parameters on startup. Supplying a URL or host and port causes the emulator to automatically attempt a connection to the specified host.

Format

```
j3270 [ -h hostname [ -p portnumber ] ] | [ -u URL ] [ -m model ]  
[ -f font ] [ -n netname ] [ -a ] [ -t timeout_value ] [ -s print_style ]  
[ -c codepage ] [ -x ]
```

where

-h <i>hostname</i>	Name of TN3270 server host.
-p <i>portnumber</i>	Port number of TN3270 server. This is the same as the port number specified as the TNServer*ListenPort in the <i>.unikirc</i> file.
-u <i>URL</i>	TN3270 host and port specified as a URL. For example tn3270://myserver.com:2002
-m <i>model</i>	Terminal model; valid values are 2 2-E 3 3E 4 4-E 5 5-E The default model is 2-E.
-f <i>font</i>	font is in the format <i>name.style.size</i> . For example -f Monospaced.PLAIN.12 .
-n <i>netname</i>	If you allow TN3270E, you may request a specific netname for this terminal.
-a	Use the alternate key map. See Section 3.5 for keyboard mapping.

- t *timeout_value*** Host inactivity *timeout_value* in seconds. MTP J3270 automatically disconnects from the host after a period of inactivity. Inactivity is determined from the last time any network activity between the host and MTP J3270 occurred. The default is not to time out, which is the same as specifying **-t 0**.
- s *print_style*** Style to use for printing. Valid values are
- | | |
|---------------------|--|
| normal | Print same as appears on screen |
| reverse | Print by reversing the display on the screen |
| whiteonblack | Print in white on a black background |
| blackonwhite | Print in black on a white background |
- The default is normal.
- c *codepage*** *codepage* to use. One of these
- Default
 - IBM-037 (US English, Portuguese, Canadian French)
 - IBM-273 (German)
 - IBM-277 (Danish, Norwegian)
 - IBM-278 (Finnish, Swedish)
 - IBM-280 (Italian)
 - IBM-281 (Japanese)
 - IBM-284 (Spanish)
 - IBM-285 (UK English)
 - IBM-297 (French)
 - IBM-500 (Belgian, Swiss German)
 - IBM-875 (Greek)
 - IBM-930 (Japanese DBCS)
 - IBM-933 (Korean DBCS)
 - IBM-935 (Simplified Chinese DBCS)
 - IBM-1025 (Bulgarian, Macedonian, Serbian Cyrillic, Russian)
 - IBM-1047 (Open edition)
- x** Excludes the use of the TN3270E protocol when connecting to the remote system. Only TN3270 is used.

3.3 3270 emulator window functions

When you start MTP J3270, this emulator window appears.




Figure 3.1 Disconnected Emulator

The menu bar of the MTP J3270 emulator allows you to


- Connect to a TN3270 system, if the emulator is in a disconnected state
- Disconnect from the currently connected system, if the emulator is in a connected state
- Print the current display
- Change the font of the display
- Get help with the keyboard mapping

When MTP J3270 is connected, it responds to keyboard input like a standard 3270 terminal. For information on how 3270 keys are mapped to keys on your PC keyboard, see [Section 3.5](#).

Note To specify an alternate key map, set a terminal *timeout_value* or connect to a region using a URL, you must invoke MTP J3270 with the appropriate parameters. See [Section 3.2](#).

3.4 Connecting to a 3270 system

If you specify the **-h hostname** or **-u URL** parameters when starting MTP J3270, the emulator automatically attempts to connect to the specified host system. If you do not specify the **-h** or **-u** parameters, follow these steps to connect to a host.

Step #	Description																
1	Invoke MTP J3270 by selecting it on the Start menu or by typing j3270 at a command prompt.																
2	<p>When the emulator window appears, click File -> Connect and set these attributes.</p>  <p style="text-align: center;">Figure 3.2 Emulator Connect Window</p> <table border="0"> <tr> <td data-bbox="326 1163 380 1188">Host</td> <td data-bbox="574 1163 711 1188">Host name.</td> </tr> <tr> <td data-bbox="326 1199 380 1224">Port</td> <td data-bbox="574 1199 1284 1257">The default is 2001. This is the same as the port number specified as the TNServer*ListenPort in the <i>.unikirc</i> file.</td> </tr> <tr> <td data-bbox="326 1268 472 1293">Terminal type</td> <td data-bbox="574 1268 867 1293">The default is 3278-2-E.</td> </tr> <tr> <td data-bbox="326 1304 493 1329">Host Codepage</td> <td data-bbox="574 1304 1333 1362">The default is Default. The supported codepages are listed in Section 3.2.</td> </tr> <tr> <td data-bbox="326 1373 537 1398">Coerce EW to EWA</td> <td data-bbox="574 1373 1370 1488">For Terminal types 3278-3, 3278-3-E, 3278-4, 3278-4-E, 3278-5 and 3278-5-E. Some TN3270 Servers do not generate correct 3270 datastreams for these terminal types. When you check this box, MTP J3270 will display the screens correctly.</td> </tr> <tr> <td></td> <td data-bbox="574 1509 1338 1568">Note This function is only available on the Connect window. There is no equivalent command line parameter.</td> </tr> <tr> <td data-bbox="326 1589 493 1614">Allow TN3270E</td> <td data-bbox="574 1589 1338 1648">Allow the use of the TN3270E protocol when connecting to the remote system.</td> </tr> <tr> <td data-bbox="326 1659 423 1684">Netname</td> <td data-bbox="574 1659 1256 1717">If you checked Allow TN3270E, you may request a specific netname for the terminal.</td> </tr> </table>	Host	Host name.	Port	The default is 2001 . This is the same as the port number specified as the TNServer*ListenPort in the <i>.unikirc</i> file.	Terminal type	The default is 3278-2-E .	Host Codepage	The default is Default . The supported codepages are listed in Section 3.2 .	Coerce EW to EWA	For Terminal types 3278-3, 3278-3-E, 3278-4, 3278-4-E, 3278-5 and 3278-5-E. Some TN3270 Servers do not generate correct 3270 datastreams for these terminal types. When you check this box, MTP J3270 will display the screens correctly.		Note This function is only available on the Connect window. There is no equivalent command line parameter.	Allow TN3270E	Allow the use of the TN3270E protocol when connecting to the remote system.	Netname	If you checked Allow TN3270E, you may request a specific netname for the terminal.
Host	Host name.																
Port	The default is 2001 . This is the same as the port number specified as the TNServer*ListenPort in the <i>.unikirc</i> file.																
Terminal type	The default is 3278-2-E .																
Host Codepage	The default is Default . The supported codepages are listed in Section 3.2 .																
Coerce EW to EWA	For Terminal types 3278-3, 3278-3-E, 3278-4, 3278-4-E, 3278-5 and 3278-5-E. Some TN3270 Servers do not generate correct 3270 datastreams for these terminal types. When you check this box, MTP J3270 will display the screens correctly.																
	Note This function is only available on the Connect window. There is no equivalent command line parameter.																
Allow TN3270E	Allow the use of the TN3270E protocol when connecting to the remote system.																
Netname	If you checked Allow TN3270E, you may request a specific netname for the terminal.																
3	Click Connect to start the connection process. A message appears if MTP J3270 fails to connect to the specified host. If you connect successfully, the first screen of the 3270 host appears.																

3.5 Specifying keyboard mapping

A real 3270 emulator has a number of special keys, such as PF Keys, Clear and Reset, that are not provided on the standard PC keyboard. MTP J3270 maps certain keys and key-combinations to the actions of these special keys.

There are two key maps, selectable when you start MTP J3270 using command line parameters. The **-a** parameter specifies the use of the alternate key map. If you omit this parameter, the standard key map is used.

Note To change to a different key map, you must stop MTP J3270 and restart it.

[Table 3.1](#) shows the supported 3270 actions and the standard and alternate key maps.

Table 3.1 MTP J3270 Key Maps

Action	Standard Key Map	Alternate Key Map
Enter	enter	enter
NewLine	<ctrl> enter	<ctrl> enter
Clear	escape	pause
Reset	<ctrl> r	Scroll lock
Erase Input	<alt> end	<alt> end
Erase EOF	<ctrl> e	<end>
Attention	<ctrl> a	<ctrl> a
SysReq	<ctrl> s	<ctrl> s
Home	<ctrl> h	<ctrl> h
Insert	<ctrl> i	<ctrl> i
Cursor Select	<ctrl> f	<ctrl> f
PA1	<ctrl> F1	<ctrl> F1
PA2	<ctrl> F2	<ctrl> F2
PA3	<ctrl> F3	<ctrl> F3
PF1 to PF12	F1 to F12	F1 to F12
PF1 to PF10	<ctrl> 1 to <ctrl> 0	<ctrl> 1 to <ctrl> 0
PF11	<ctrl> -	<ctrl> -
PF12	<ctrl> +	<ctrl> +
PF13 to PF24	<shift> F1 to <shift> F12	<shift> F1 to <shift> F12

3.6 Using MTP J3270 in DBCS mode

To use MTP J3270 in DBCS (Double-byte Character Set) mode, choose one of the available DBCS codepages on the Connect window or specify a DBCS codepage using the `-c` parameter of the `j3270` command.

3.6.1 Available 3270 field types

When running in DBCS mode, each 3270 field is one of these

- A pure single-byte field
- A pure double-byte field
- A mixed single- and double-byte field known as a SOSI (Shift-Out, Shift-In) field

3.6.1.1 Restrictions on a pure single-byte field

A pure single-byte field may only contain single-byte characters. Any attempt to type a character into a pure single-byte field that is not a single-byte character results in a terminal alarm.

3.6.1.2 Restrictions on a pure double-byte field

A pure double-byte field may only contain double-byte characters. A double-byte character occupies two display positions and is twice the physical width of a single-byte character. Any attempt to type a character that is not a double-byte character into a pure double-byte field results in a terminal alarm.

A character is considered double-byte if its representation in the selected host codepage is two bytes.

3.6.1.3 Restrictions on mixed (SOSI) fields

A SOSI (Shift-Out, Shift-In) field may contain both single- and double-byte characters. You must enclose all double-byte characters in a SOSI field within a pair of SOSI characters.

- SO and SI characters each occupy a display position.
- A SO character appears as a “less than” symbol, `<`.
- A SI character appears as a “greater than” symbol, `>`.
- SO and SI characters are inserted automatically as a terminal user types. The terminal user does not have to enter them.
- Any keyboard entry operation that would leave DBCS characters outside an enclosing SOSI pair is invalid and is rejected with a terminal alarm. For example, an attempt to delete a SI character that would leave a DBCS character immediately adjacent to an SBCS (single-byte character set) character.
- An attempt to enter DBCS characters that does not leave room for the required SO and SI characters to be automatically inserted in the field is rejected with a terminal alarm. For example, an attempt to enter a DBCS character in the last two display positions of a SOSI field.

3.7 Making an association with an Internet browser

You can configure some web browsers so that any links to TN3270 hosts are started with MTP J3270. When you click on the link, the browser starts MTP J3270 and attempts to make a connection to the TN3270 system.

On your Windows system, associate files of type URL:TN3270 Protocol with **j3270 -u**. You must have MTP J3270 in your path or you must specify the complete pathname where the **j3270** executable is installed. Refer to Windows Help for instructions on associating files.

Index

Numerics

3270 terminal emulator. *See* MTP J3270

C

codepages

supported 3-2

commands

conventions 1-2

j3270 3-1

notation conventions 1-2

connecting to a host

using a URL 3-1

using command line parameters 3-1

using the emulator window 3-3, 3-4

conventions

commands 1-2

text 1-1

D

DBCS

3270 field types 3-6

double-byte field restrictions 3-6

enabling in MTP J3270 3-6

single-byte field restrictions 3-6

SOSI field restrictions 3-6

Double Byte Character Set. *See* DBCS

double-byte field

definition 3-6

restrictions 3-6

E

emulator

connect window 3-4

window functions 3-3

H

host name, specifying 3-1, 3-4

I

installing MTP J3270 2-1

Internet browser

associating MTP J3270 3-7

J

j3270 command 3-1

Java Runtime Environment (JRE) 2-1

K

keyboard mapping 3-5

M

MTP J3270

allow TN3270E protocol 3-4

associating with an Internet browser 3-7

coerce EW to EWA 3-4

connecting to a host

using a URL 3-1

using command line parameters 3-1

using the emulator window 3-3

emulator connect window 3-4

emulator window functions 3-3

exclude use of TN3270E protocol 3-2

executable 2-1

installing 2-1

invoking 3-1

key maps 3-5

prerequisites 2-1

specifying

codepage 3-2, 3-4

host inactivity timeout 3-2

keyboard map 3-5

netname 3-4

print style 3-2

terminal model 3-4

TN3270 server host 3-1, 3-4

TN3270 server port number 3-1, 3-4

starting 3-1

starting from Start Menu 2-2

supported platforms 2-1

N

netname, specifying 3-4

notation conventions 1-2

P

port number, specifying 3-1, 3-4

print style, specifying 3-2

S

Shift-Out, Shift-In field. *See* SOSI field

single-byte field

definition 3-6

restrictions 3-6

SOSI field

definition 3-6

restrictions 3-6

T

terminal

MTP J3270 emulator. *See* MTP J3270

terminal model, specifying [3-4](#)

text conventions [1-1](#)

timeout value, specifying [3-2](#)

U

unikixtnemux server [2-1](#)

URL file types, associating with MTP J3270
[3-7](#)

URL, specifying [3-1](#)