

SUN SEEBEYOND

**eGATE™ API KIT FOR JMS IQ
MANAGER (COM+ EDITION)**

Release 5.1.3



Copyright © 2007 Sun Microsystems, Inc., 4150 Network Circle, Santa Clara, California 95054, U.S.A. All rights reserved. Sun Microsystems, Inc. has intellectual property rights relating to technology embodied in the product that is described in this document. In particular, and without limitation, these intellectual property rights may include one or more of the U.S. patents listed at <http://www.sun.com/patents> and one or more additional patents or pending patent applications in the U.S. and in other countries. U.S. Government Rights - Commercial software. Government users are subject to the Sun Microsystems, Inc. standard license agreement and applicable provisions of the FAR and its supplements. Use is subject to license terms. This distribution may include materials developed by third parties. Sun, Sun Microsystems, the Sun logo, Java, Sun Java Composite Application Platform Suite, SeeBeyond, eGate, eInsight, eVision, eTL, eXchange, eView, eIndex, eBAM, eWay, and JMS are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. in the U.S. and other countries. Products bearing SPARC trademarks are based upon architecture developed by Sun Microsystems, Inc. UNIX is a registered trademark in the U.S. and other countries, exclusively licensed through X/Open Company, Ltd. This product is covered and controlled by U.S. Export Control laws and may be subject to the export or import laws in other countries. Nuclear, missile, chemical biological weapons or nuclear maritime end uses or end users, whether direct or indirect, are strictly prohibited. Export or reexport to countries subject to U.S. embargo or to entities identified on U.S. export exclusion lists, including, but not limited to, the denied persons and specially designated nationals lists is strictly prohibited.

Copyright © 2007 Sun Microsystems, Inc., 4150 Network Circle, Santa Clara, California 95054, Etats-Unis. Tous droits réservés. Sun Microsystems, Inc. détient les droits de propriété intellectuelle relatifs à la technologie incorporée dans le produit qui est décrit dans ce document. En particulier, et ce sans limitation, ces droits de propriété intellectuelle peuvent inclure un ou plus des brevets américains listés à l'adresse <http://www.sun.com/patents> et un ou les brevets supplémentaires ou les applications de brevet en attente aux Etats - Unis et dans les autres pays. L'utilisation est soumise aux termes de la Licence. Cette distribution peut comprendre des composants développés par des tierces parties. Sun, Sun Microsystems, le logo Sun, Java, Sun Java Composite Application Platform Suite, Sun, SeeBeyond, eGate, eInsight, eVision, eTL, eXchange, eView, eIndex, eBAM et eWay sont des marques de fabrique ou des marques déposées de Sun Microsystems, Inc. aux Etats-Unis et dans d'autres pays. Toutes les marques SPARC sont utilisées sous licence et sont des marques de fabrique ou des marques déposées de SPARC International, Inc. aux Etats-Unis et dans d'autres pays. Les produits portant les marques SPARC sont basés sur une architecture développée par Sun Microsystems, Inc. UNIX est une marque déposée aux Etats-Unis et dans d'autres pays et licenciée exclusivement par X/Open Company, Ltd. Ce produit est couvert à la législation américaine en matière de contrôle des exportations et peut être soumis à la réglementation en vigueur dans d'autres pays dans le domaine des exportations et importations. Les utilisations, ou utilisateurs finaux, pour des armes nucléaires, des missiles, des armes biologiques et chimiques ou du nucléaire maritime, directement ou indirectement, sont strictement interdites. Les exportations ou réexportations vers les pays sous embargo américain, ou vers des entités figurant sur les listes d'exclusion d'exportation américaines, y compris, mais de manière non exhaustive, la liste de personnes qui font objet d'un ordre de ne pas participer, d'une façon directe ou indirecte, aux exportations des produits ou des services qui sont régis par la législation américaine en matière de contrôle des exportations et la liste de ressortissants spécifiquement désignés, sont rigoureusement interdites.

Part Number: 820-0946-10

Version 20070412115952

Contents

Chapter 1

Introduction	12
About This Document	12
What's in This Document	12
Intended Audience	12
Text Conventions	13
Screenshots	13
Related Documents	13
Sun Microsystems, Inc. Web Site	13
Documentation Feedback	14

Chapter 2

Installing the eGate API Kit	15
Supported Operating Systems	15
System Requirements	15
Supported Compilers	15
Installing the eGate API Kit	16
Post-Installation Instructions	17

Chapter 3

JMS and COM+ Implementation Overview	18
About the Sun SeeBeyond JMS IQ Manager	18
The Java CAPS JMS Interface	18
Java CAPS Project Considerations	20
Viewing JMS IQ Manager Port Numbers	20
About the Java Messaging Service	21
JMS Messages	21
Message Header Fields	21
Message Properties	22
Message Body (Payload)	22
JMS Messaging Types	23

Publish/Subscribe Projects	23
Point-to-Point Projects	24
Request-Reply Projects	24
About the COM+ Interface	25
Creating Destinations	26
XA Compliance	26
Message Selectors	26
Multi-Threaded Apartments	26
Sample Code	26
The Compensating Resource Manager (CRM)	27
About Compensating Resource Managers	27
CRM Architecture	27
Two-phase Commit Protocol	28
Implementing the Compensating Resource Manager	28
Configuring the Compensating Resource Manager	29
Step 1: Add a New Component Application	29
Step 2: Installing the stc_mscom Component	31
Step 3: Configuring the stc_mscom Component	33
Step 4: Configuring the STC_MSCOM.Compensator	34
Step 5: Configuring the STC_MSCOM XA Connection Factories	36

Chapter 4

COM+ Object Reference	38
About the Java CAPS JMS Interface for Applications in COM+	39
The COM+ Object Model	39
Wrapper Functions for COM+ Applications	40
COM+ API Correspondence with JMS	41
Viewing the COM+ API	42
Creating Destinations	43
COM+ Constants	43
AcknowledgeMode Constants	43
DeliveryMode Constants	44
Message Constants	44
Priority Constants	45
BytesMessage Object	45
BytesMessage Properties	46
BytesMessage Methods	46
Acknowledge	47
ClearBody	47
ClearProperties	48
GetProperty	48
PropertyExists	48
ReadBoolean	49
ReadByte	49
ReadBytes	50
ReadChar	50
ReadDouble	50

ReadFloat	51
ReadInt	51
ReadLong	51
ReadShort	52
ReadUnsignedByte	52
ReadUnsignedShort	52
ReadUTF	53
Reset	53
setProperty	54
WriteBoolean	54
WriteByte	54
WriteBytes	55
WriteChar	55
WriteDouble	56
WriteFloat	56
WriteInt	56
WriteLong	57
WriteObject	57
WriteShort	57
WriteUTF	58
Connection Object	58
Connection Properties	58
Connection Methods	58
Start	59
Stop	59
ConnectionFactory Object	59
ConnectionFactory Properties	59
ConnectionMetaData Object	60
MapMessage Object	60
MapMessage Properties	60
MapMessage Object Methods	61
Acknowledge	62
ClearBody	62
ClearProperties	62
GetBoolean	63
GetByte	63
GetBytes	63
GetChar	64
GetDouble	64
GetFloat	65
GetInt	65
GetLong	66
GetObject	66
GetProperty	66
GetShort	67
GetString	67
ItemExists	67
PropertyExists	68
SetBoolean	68
SetByte	69
SetBytes	69

SetChar	70
SetDouble	70
SetFloat	70
SetInt	71
SetLong	71
SetObject	72
SetProperty	72
SetShort	72
SetString	73
message Object	73
message Properties	73
message Methods	74
Acknowledge	74
ClearBody	75
ClearProperties	75
GetProperty	75
PropertyExists	76
SetProperty Method	76
MessageConsumer Object	77
MessageConsumer Properties	77
MessageConsumer Methods	77
Close	77
ReceiveMessage	77
ReceiveNoWait	78
MessageListener Object	78
MessageProducer Object	78
MessageProducer Properties	79
Queue Object	79
Queue Properties	79
Queue Methods	80
ToString	80
QueueBrowser Object	80
QueueConnection Object	80
QueueConnection Properties	80
QueueConnection Methods	81
CreateQueueSession	81
Start	81
Stop	82
QueueConnectionFactory Object	82
QueueConnectionFactory Properties	82
QueueConnectionFactory Methods	82
CreateQueueConnection	83
CreateQueueConnectionEx	83
QueueReceiver Object	83
QueueReceiver Properties	84
QueueReceiver Methods	84
Close	84
Receive	84

ReceiveNoWait	85
QueueRequestor Object	85
QueueRequestor Methods	85
Close	86
Create	86
Request	86
QueueSender Object	87
QueueSender Properties	87
QueueSender Methods	88
Send	88
QueueSession Object	89
QueueSession Properties	89
QueueSession Object Methods	89
Commit	89
CreateBytesMessage	90
CreateMapMessage	90
CreateMessage	90
CreateQueue	91
CreateReceiver	91
CreateSender	92
CreateStreamMessage	92
CreateTemporaryQueue	92
CreateTextMessage	93
Recover	93
Rollback	93
Run	94
session Object	94
session Properties	94
session Methods	95
Commit	95
CreateBytesMessage	95
CreateMapMessage	96
CreateMessage	96
CreateStreamMessage	96
CreateTextMessage	97
Recover	97
Rollback	97
Run	98
StreamMessage Object	98
StreamMessage Properties	98
StreamMessage Methods	99
Acknowledge	100
ClearBody	100
ClearProperties	100
GetProperty	101
PropertyExists	101
ReadBoolean	102
ReadByte	102
ReadBytes	102
ReadChar	103
ReadDouble Method	103

ReadFloat	103
ReadInt	104
ReadLong Method	104
ReadObject	104
ReadShort	105
ReadString	105
Reset	105
SetProperty	106
WriteBoolean	106
WriteByte	106
WriteBytes	107
WriteChar	107
WriteDouble	108
WriteFloat	108
WriteInt	108
WriteLong	109
WriteObject	109
WriteShort	109
WriteString	110
TemporaryQueue Object	110
TemporaryQueue Properties	110
TemporaryQueue Object Methods	111
Delete	111
ToString	111
TemporaryTopic Object	111
TemporaryTopic Properties	112
TemporaryTopic Methods	112
Delete	112
ToString	112
TextMessage Object	113
TextMessage Properties	113
TextMessage Methods	114
Acknowledge	114
ClearBody	114
ClearProperties	114
GetProperty	115
PropertyExists	115
SetProperty	116
Topic Object	116
Topic Properties	116
Topic Methods	116
ToString	117
TopicConnection Object	117
TopicConnection Properties	117
TopicConnection Methods	117
CreateTopicSession	117
Start	118
Stop	118
TopicConnectionFactory Object	119
TopicConnectionFactory Properties	119

TopicConnectionFactory Methods	119
CreateTopicConnection	119
CreateTopicConnectionEx	120
TopicPublisher Object	120
TopicPublisher Properties	120
TopicPublisher Methods	121
Publish	121
TopicRequestor Object	122
TopicRequestor Methods	122
Close	122
Create	122
Request	123
TopicSession Object	123
TopicSession Properties	124
TopicSession Methods	124
Commit	124
CreateBytesMessage	125
CreateDurableSubscriber	125
CreateMapMessage	126
CreateMessage	126
CreatePublisher	126
CreateStreamMessage	127
CreateSubscriber	127
CreateTemporaryTopic	128
CreateTextMessage	128
CreateTopic	128
Recover	129
Rollback	129
Run	130
Unsubscribe	130
TopicSubscriber Object	130
TopicSubscriber Properties	131
TopicSubscriber Methods	131
Close	131
Receive	132
ReceiveNoWait	132
XAQueueConnection Object	132
XAQueueConnection Properties	133
XAQueueConnection Methods	133
CreateQueueSession	133
CreateXAQueueSession	134
Start	134
Stop	134
XAQueueConnectionFactory Object	135
XAQueueConnectionFactory Object Properties	135
XAQueueConnectionFactory Methods	135
CreateQueueConnection	135
CreateQueueConnectionEx	136
CreateXAQueueConnection	136
CreateXAQueueConnectionEx	136

XAQueueSession Object	137
XAQueueSession Properties	137
XAQueueSession Methods	137
Commit	138
CreateBytesMessage	138
CreateMapMessage	138
CreateMessage	139
CreateStreamMessage	139
CreateTextMessage	139
Recover	140
Rollback	140
Run	141
XASession Object	141
XASession Object Properties	141
XASession Object Methods	141
Commit	142
CreateBytesMessage	142
CreateMapMessage	142
CreateMessage	143
CreateStreamMessage	143
CreateTextMessage	143
Recover	144
Rollback	144
Run	145
XATopicConnection Object	145
XATopicConnection Properties	145
XATopicConnection Methods	145
CreateTopicSession	146
CreateXATopicSession	146
Start	147
Stop	147
XATopicConnectionFactory Object	147
XATopicConnectionFactory Properties	148
XATopicConnectionFactory Methods	148
CreateTopicConnection	148
CreateTopicConnectionEx	149
CreateXATopicConnection	149
CreateXATopicConnectionEx	149
XATopicSession Object	150
XATopicSession Properties	150
XATopicSession Methods	150
Commit	151
CreateBytesMessage	151
CreateMapMessage	151
CreateMessage	152
CreateStreamMessage	152
CreateTextMessage	152
Recover	153
Rollback	153
Run	154
Error Codes	154

IErrorInfo Methods	154
HRESULT Errors	154
Error Value Constants	155

Chapter 5

Working with the COM+ API Samples **157**

About the COM+ Samples 157

Implementing the Java CAPS Projects 158

 Importing the Sample Project 158

 Creating the Environment 159

 Deploying the Projects 159

Building the Sample COM+ Application 159

 Setting up the Directory Structure 160

 Configuring the Sample Environment 160

 Building the Sample Applications 160

Building the CRM Sample Application 161

 Creating a Database for the CRM Sample 161

 Configuring and Building the CRM Sample 163

 Creating the CRM Sample Application 164

Running the Sample COM+ Applications 165

Index **168**

Introduction

This chapter introduces you to this guide, its general purpose and scope, and its organization. It also provides sources of related documentation and information.

What's in This Chapter

- [About This Document](#) on page 12
- [Related Documents](#) on page 13
- [Sun Microsystems, Inc. Web Site](#) on page 13
- [Documentation Feedback](#) on page 14

1.1 About This Document

This user's guide describes how to install and use the eGate™ API Kit to create COM+ applications that connect to Sun Java™ Composite Platform Suite (CAPS) Projects via Java™ Message Service (JMS).

1.1.1 What's in This Document

This document includes the following chapters:

- [Chapter 2 "Installing the eGate API Kit"](#) describes how to install the eGate API Kit and its samples.
- [Chapter 3 "JMS and COM+ Implementation Overview"](#) gives information about the JMS IQ Manager and how the COM+ API interfaces with it.
- [Chapter 4 "COM+ Object Reference"](#) describes how to develop COM+ applications to access the Sun SeeBeyond JMS IQ Manager in Java CAPS Project.
- [Chapter 5 "Working with the COM+ API Samples"](#) describes the COM+ samples and how to configure and implement them.

1.1.2 Intended Audience

This guide is intended for developers who are familiar with programming applications that interface through JMS.

1.1.3 Text Conventions

The following conventions are observed throughout this document.

Table 1 Text Conventions

Text Convention	Used For	Examples
Bold	Names of buttons, files, icons, parameters, variables, methods, menus, and objects	<ul style="list-style-type: none">▪ Click OK.▪ On the File menu, click Exit.▪ Select the eGate.sar file.
Monospaced	Command line arguments, code samples; variables are shown in <i>bold italic</i>	java -jar <i>filename</i> .jar
Blue bold	Hypertext links within document	See Related Documents on page 13
<u>Blue underlined</u>	Hypertext links for Web addresses (URLs) or email addresses	http://www.sun.com

1.1.4 Screenshots

Depending on what products you have installed, and how they are configured, the screenshots in this document may differ from what you see on your system.

1.2 Related Documents

For more information about eGate Integrator, refer to the following documents:

- *Sun SeeBeyond Java Composite Application Platform Suite Installation Guide*
- *Sun SeeBeyond eGate Integrator User's Guide*
- *Sun SeeBeyond eGate Integrator JMS Reference Guide*
- *Sun SeeBeyond eGate Integrator System Administration Guide*
- *Sun SeeBeyond Java Composite Application Platform Suite Deployment Guide*

1.3 Sun Microsystems, Inc. Web Site

The Sun Microsystems web site is your best source for up-to-the-minute product news and technical support information. The site's URL is:

<http://www.sun.com>

1.4 Documentation Feedback

We appreciate your feedback. Please send any comments or suggestions regarding this document to:

CAPS_docsfeedback@sun.com

Installing the eGate API Kit

This chapter describes the process of installing the eGate API Kit.

What's in This Chapter

- [Supported Operating Systems](#) on page 15
- [System Requirements](#) on page 15
- [Supported Compilers](#) on page 15
- [Installing the eGate API Kit](#) on page 16
- [Post-Installation Instructions](#) on page 17

2.1 Supported Operating Systems

For information about supported operating systems, refer to the `eGateAPIKit_Readme.txt`.

2.2 System Requirements

The eGate API Kit has the same system requirements as eGate Integrator. For information, refer to the *Sun SeeBeyond Java Composite Application Platform Suite Installation Guide*.

In addition, you need a development environment with a compiler that is compatible with the selected O/S; for example, Microsoft Visual .Net 2003.

2.3 Supported Compilers

The eGate API Kit COM+ API is compatible with .Net 2003 version 7.1 on a Windows platform. If you use a different compiler, be aware that some compilers are incompatible with eGate.

2.4 Installing the eGate API Kit

The procedure below describes an overview of how to install the eGate API Kit. For detailed installation instructions, refer to the *Sun Java SeeBeyond Composite Application Platform Suite Installation Guide*.

Before you install the eGate API Kit, install and download the following items using the Java CAPS Installer:

- Repository
- eGate Integrator
- Enterprise Designer
- Enterprise Manager
- Logical Host

The procedure below describes how to install the following items for eGate API Kit:

- the software
- the documentation
- the sample Enterprise Designer Projects and the code samples

To install eGate API Kit

- 1 Launch the Java Composite Application Platform Suite Installer.
- 2 In the **Administrator** page, click **Click to install additional products**.
- 3 In the list of products to install, select the following:
 - ♦ **eGate API Kit > eGate_APIKit_<OS>** where <OS> is the operating system you are installing on (to install the eGate API Kit software)
 - ♦ **Documentation > eGateAPIKitDocs** (optional—to install the eGate API Kit documentation and samples)
- 4 In the **Administrator > Upload** page, select the following items and click **Next** after each SAR file is selected:
 - ♦ **eGate_APIKit_<OS>.sar** (for example, **eGate_APIKit_SunOS.sar**).
 - ♦ **eGateAPIKitDocs.sar**

When the installation is finished, the “Installation Completed” message appears.

- 5 In the **Downloads** page, select **API kit for <OS>** (where <OS> is the operating system you are installing on), select a location for the **.zip** file to be saved, and then extract the file.
- 6 To view the documentation:
 - A Click the **Documentation** tab, and then click **Add-ons**.
 - B In the product list, click **Sun SeeBeyond eGate(TM) API Kit**.

- C Click the PDF icon next to the document or HTML help system you want to view.
- 7 To download the sample Project and code samples:
 - A Click the **Documentation** tab, and then click **Add-ons**.
 - B In the product list, click **Sun SeeBeyond eGate(TM) API Kit**.
 - C Click the zip file icon next to **Sample Projects**, and then click **Open**.
 - D Extract the files to a temporary directory on your computer.
 - E Navigate to the temporary directory.
 - F Extract **ProjectSamples.zip**.
 - G For Windows, extract **CodeSamples.zip**. For UNIX systems, untar **CodeSamplesUNIX.tar**.

For information about importing and using the sample Projects, refer to [Chapter 5](#) “Working with the COM+ API Samples”.

2.5 Post-Installation Instructions

After the eGate API Kit installation, do the following before you start building applications:

- 1 Locate the **stc_mscom.dll**, **stc_msclient.dll**, **stc_mscommon.dll**, **stc_msapi.dll** files in the directory on the external system where the eGate API Kit is installed.
- 2 From the command line of the external system, register the file **stc_mscom.dll** into the Windows Registry as illustrated below:

```
regsvr32 <root>\apikit\jms\complus_api\stc_mscom.dll
```

JMS and COM+ Implementation Overview

The eGate API Kit provides an interface for external applications to exchange data with Java CAPS Projects via the Sun SeeBeyond JMS IQ Manager. This chapter gives an overview of JMS and the Sun SeeBeyond JMS IQ Manager, and provides implementation and CRM information.

What's in This Chapter

- [About the Sun SeeBeyond JMS IQ Manager](#) on page 18
- [About the Java Messaging Service](#) on page 21
- [About the COM+ Interface](#) on page 25
- [The Compensating Resource Manager \(CRM\)](#) on page 27

3.1 About the Sun SeeBeyond JMS IQ Manager

This section provides an overview of the Sun SeeBeyond JMS IQ Manager, including JMS version support and considerations for the Java CAPS Project. This section also describes how to find the port numbers used for a runtime Project.


3.1.1 The Java CAPS JMS Interface

For those of you unfamiliar with JMS interfaces, this section describes the Java CAPS JMS interface. The Java CAPS JMS consists of the following components:

- **Message Service Client** - The external application.
- **Message Service** - The data container and route.
- **API Kit Connection** - The link between eGate and the external system.


Figure 1 illustrates the communication between each component.

Figure 1 Message Service Communication Architecture



In Figure 2, all necessary components have been isolated onto a separate system. While this separation is not mandatory, the combinations of components that reside together on various systems change depending upon your needs.

Figure 2 Java CAPS TCP/IP Communication Architecture



The following components are required:

- Repository
- Logical Host

- Sun SeeBeyond Integration Server (IS)
- External System (Message Service Client file)
- Database Server (Data Repository)

Important: From this point forward, when referring to a machine, the above naming conventions are used. Remember that multiple components may reside on the same machine. For example, the Logical Host and the External System may exist on one physical machine.

3.1.2 Java CAPS Project Considerations

To enable your application to communicate with a runtime JMS IQ Manager, consider the following:

- The message destination names and the names of the components used must coincide.
- Your JMS application must use the expected data format, the name of the message destination, and the host name and port number of the JMS IQ Manager (see “Viewing JMS IQ Manager Port Numbers” for port number information).
- The methods used must correspond to the expected data format.

3.1.3 Viewing JMS IQ Manager Port Numbers

The default port number for JMS IQ Managers is 18007. The default port number for SSL is 18008. To view the port numbers for your runtime Java CAPS Project, use the Domain Manager as described in the procedure below.

To view JMS IQ Manager port numbers

- 1 Navigate to the folder where the Java CAPS Logical Host is installed.
- 2 Double-click **domainmgr.bat**. The Domain Manager window appears.

Figure 3 Viewing Runtime JMS IQ Manager Port Numbers

Properties / Domain Names		domain1
Server Running		✓
Admin Port		18000
HTTP		18001
ORB		18002
IMQ		N/A
HTTPS		18004
ORB SSL		18005
ORB MutualAuth		18006
IQ Manager		18007
IQ Manager SSL		18008
Windows Service Installed		✗

The **IQ Manager** property specifies the JMS IQ Manager port; the **IQ Manager SSL** property specifies the JMS IQ Manager SSL port.

3.2 About the Java Messaging Service

This section provides an overview of JMS messages and some different types of messaging scenarios.

3.2.1 JMS Messages

The message is defined by the message structure, the header, and the properties. All of the data in a JMS application are expressed using messages, while the additional components exist to facilitate the transferal of messages. JMS messages are composed of the following:

- **Header** - The header fields contain values used by both clients and providers to identify and route messages. All messages support the same set of header fields.
- **Properties** - The properties provide a way to add optional header fields to messages. They can be application-specific, standard, or provider-specific.
- **Body (or Payload)** - JMS supports different types of payload. The current JMS eWay Connection supports bytes and text messaging.

Message Header Fields

When a message is received by the client, the message's header is transmitted in its entirety. The fields in the header are described below.

- **JMSDestination** - The destination to which the message is being sent.
- **JMSDeliveryMode** - The mode of delivery when the message was sent. The two modes of delivery are *non-persistent* and *persistent*. Non-persistent mode causes the lowest overhead because it does not require the message to be logged to stable storage; however, non-persistent messages can be lost. Persistent mode instructs the provider to ensure that messages are not lost in transit due to provider failure.
- **JMSMessageID** - A value that uniquely identifies each message sent by a provider. The JMSMessageID is a String value that should contain a unique key for identifying messages in a historical repository. The provider must provide the scope of uniqueness. The JMSMessageID must start with the **ID:** prefix.
- **JMSTimestamp** - The time that a message is handed off to a provider to be sent. It is not the actual transmission time because the send may occur later due to pending transactions.
- **JMSExpiration** - The time that is calculated as the sum of the time-to-live value specified on the send method and the current GMT value. After the send method is returned, the message's JMSExpiration header field contains this value. If the time-to-live is specified as zero, expiration is also set to zero and the message does not expire.

- **JMSRedelivered** - An indicator of whether the message was re-delivered to the consumer. If the header is “true”, the message is re-delivered; if the header is false, the message is not. The message might be marked as re-delivered if a consumer fails to acknowledge delivery of the message, or if the JMS provider is uncertain that the consumer received the message.

```
boolean isRedelivered = message.getJMSRedelivered();
```

- **JMSPriority** - The message’s priority. There is a ten-level priority value system, with 0 as the lowest priority and 9 as the highest. Priorities between 0-4 are gradations of normal priority, while 5-9 are expedited priorities.
- **JMSReplyTo** - The `javax.jms.Destination`, which indicates the address to which to reply and enables the consumer to reply to a message associated with a specific producer.

```
message.setJMSReplyTo(topic);  
...  
Topic topic = (Topic) message.getJMSReplyTo();
```

- **JMSCorrelationID** - Associates the current message with a previous message or application-specific ID. Usually the `JMSCorrelationID` is used to tag a message as a reply to a previous message identified by a `JMSMessageID`. The `JMSCorrelationID` can contain any value and is not limited to `JMSMessageID`.

```
message.setJMSCorrelationID(identifier)  
...  
String correlationid = message.getJMSCorrelationID();
```

Message Properties

Properties allow a client to have the JMS provider select messages based on application-specific criteria using message selectors. The property values must be set prior to sending a message.

Message Body (Payload)

The full JMS specification defines six types of message body, also called *payload*. Each form is defined by a message interface. Currently, the following interfaces are supported by the eGate API Kit:

- **Message** - This message type carries no payload, and is generally used for event notification.
- **BytesMessage** - A message that carries a byte array as its payload, and is often used in cases where JMS is simply used as a transport between systems. This message type is for encoding a body to match an existing message format. It can be used for exchanging data in an application’s native format.
- **MapMessage** - A message that carries a set of name and value pairs as its payload, and is often used for delivering keyed data. The names are Strings and the values are Java primitive data types.
- **StreamMessage** - A message that carries a stream of primitive Java types (such as **char**, **double**, and **int**) as its payload, and is often used when delivering primitive application data in a fixed order. This message type also writes the data type

information along with the value of the type and enforces a set of strict conversion rules.

- **TextMessage** - A message that carries a string (of type `java.lang.String`) as its payload, and is used for exchanging both text messages and XML documents. As such, it is the most frequently used message type.

3.2.2 JMS Messaging Types

This section discusses characteristics of the following types of messaging scenarios.


- **Publish/Subscribe Projects** on page 23
- **Point-to-Point Projects** on page 24
- **Request-Reply Projects** on page 24

Publish/Subscribe Projects

The Publish/Subscribe model provides the means for a message producer or publisher to distribute a message to one or more consumers or subscribers. There are three important points to the Publish/Subscribe model:

- Messages are delivered to consumers without requiring a request. They are pushed via a channel referred to as a topic. The topic is considered a destination to which producers publish and consumers subscribe. Messages are automatically pushed to all qualified consumers.
- There is no coupling of the producers to the consumers. Both subscribers and publishers can be dynamically added at runtime, allowing the system to change as needed.
- Each client receives a copy of the messages that have been published to those topics to which it subscribes. Multiple subscribers can receive messages published by one producer.

Figure 4 The Publish/Subscribe Schema




Point-to-Point Projects

Point-to-Point messaging is based on the sending of a message to a named destination (as is the publish/subscribe model). There is no direct coupling of the producers to the consumers. One main difference between point-to-point and publish/subscribe messaging is that in the first, messages are delivered without consideration of the current connection status of the receiver. In a point-to-point model, the producer is referred to as a sender while the consumer is referred to as a receiver. The following characteristics apply:

- Message exchange takes place via a queue instead of a topic. The queue acts as a destination to which producers send messages and a source from which receivers consume messages.
- Each message is delivered to only one receiver. Multiple receivers may connect to a queue, but each message in the queue may only be consumed by one of the queue's receivers.
- The queue delivers messages to consumers in the order that they were placed in the queue by the Message Service. As messages are consumed, they are removed from the "front of the line".
- Receivers and senders can be added dynamically at runtime, allowing the system to grow as needed.

Figure 5 Point to Point




Request-Reply Projects

JMS provides the `JMSReplyTo` message header field for specifying the destination to which the reply to a message is to be sent. The `JMSCorrelationID` header field of the reply can be used to reference the original request. Temporary queues and topics can be used as unique destinations for replies. It can be implemented so that one message yields one reply, or one message yields many replies.

Figure 6 The Request-Reply Schema

Point to Point - Request Reply (One to One)



Following is a scenario that provides an example of how a request-reply project could be configured.

- 1 A request is received by the **JMS Connection**, which is controlled by the JMS IQ Manager, and the JMSReplyTo property is read into the internally directed by the Collaboration.
- 2 eGate reads in the request from **SampleTopicRequestor**, and appends a message to the end of the message for verification's sake.
- 3 The **SeeBeyond JMS IQ Manager** sends the message to a Temporary Topic via the JMS Connection.
- 4 The reply subscriber receives the message.
- 5 When the **Message Service** users disconnect, the temporary topic is destroyed.

3.3 About the COM+ Interface

The COM+ Edition of the eGate API Kit supports the *Java Messaging Service Specification version 1.0.2b*. This section provides overview information for the following topics:

- **Creating Destinations** on page 26
- **XA Compliance** on page 26
- **Message Selectors** on page 26
- **Multi-Threaded Apartments** on page 26
- **Sample Code** on page 26

3.3.1 Creating Destinations

Destinations do not need to be created separately; they are created through the `QueueSession.CreateQueue()` and `QueueSession.CreateTopic()` functions. If these destinations do not exist, they are created automatically.

3.3.2 XA Compliance

XA compliance is achieved when cooperating software systems contain sufficient logic to ensure that the transfer of a single unit of data between those systems is neither lost nor duplicated because of a failure condition in one or more of the cooperating systems. This is known as a transactional environment.

For more information on XA, see the *Sun SeeBeyond eGate Integrator User's Guide*.

3.3.3 Message Selectors

A message selector allows a client to specify the messages in which the client is interested using the message header. Only messages for which the headers and properties match the selector are delivered. The semantics of not delivered differ depending on the message consumer implemented. Message selectors cannot reference message body values.

The message selector matches a message, provided the selector evaluates to "true", when the message's header field and the property values are substituted for the corresponding identifiers within the selector.

For more information about Message Selection, see the *Java Messaging Service Specification version 1.0.2b*.

3.3.4 Multi-Threaded Apartments

The COM+ components support the multi-threaded apartment model (MTA). Multiple threads in the application can use the COM+ component at the same time; for example, multiple threads can create sessions, send messages and wait for messages to be received. It should be noted that the multi-threaded model follows the multi-threaded programming model outlined in the *Java Messaging Service Specification version 1.0.2b*. In essence, this defines the session and its associated objects as single threaded contexts.

For the JMS API in COM+, all the components were built using Microsoft Visual Studio .Net 2003 with the `msvc71.dll` and the `msvcr71.dll` libraries. Applications that use the COM+ components should be compiled with the runtime libraries option: "multi-threaded DLL" to assure the same runtime libraries are used.

3.3.5 Sample Code

The eGate API Toolkit provides a sample download that includes code samples for creating interfaces to the Java CAPS JMS with COM+. For information about implementing the sample code, see ["Working with the COM+ API Samples" on page 157](#).

3.4 The Compensating Resource Manager (CRM)

This section provides basic information about the CRM and also provides instructions for configuring the CRM for the eGate API Toolkit. It includes the following topics:

- [About Compensating Resource Managers](#) on page 27
- [Implementing the Compensating Resource Manager](#) on page 28
- [Configuring the Compensating Resource Manager](#) on page 29

3.4.1 About Compensating Resource Managers

A *Compensating Resource Manager* can be described as a COM+ object that uses a set of tools (CRM facility) that allow you to create resource managers. This allows you to perform non-database operations (such as generating a file) as part of a transaction.

A *distributed transaction* is a transaction that involves multiple independent resource managers. For example, it might include an Oracle database at the corporate office and a SQL Server database at the partner's warehouse. The involved resource managers attempt to complete and commit their part of the transaction. If any part of the transaction fails, all resource managers roll back their respective updates.

This is accomplished using the two-phase commit protocol. In this protocol, the activity of one or more resource managers is controlled by a separate piece of software called a transaction coordinator.

CRM Architecture

A minimum of two COM components must be implemented to create a CRM scenario. At least one CRM Worker and a CRM Compensator are required. The COM+ CRM functionality provides the CRM clerk and a durable log file. The CRM Worker contains the application-level code that directs the business logic employed by the Compensating Resource Manager. If the CRM writes XML files, the CRM Worker is likely to contain a **WriteToFile** method, along with a COM+ implementation of JMS interfaces to the message service. The CRM Worker acts as a transacted COM+ component that is configured to require a transaction. When an application activates a CRM Worker component, the CRM Worker instantiates the CRM clerk object, and uses that CRM clerk to register a compensator component.

The functionality provided by SeeBeyond's implementation of CRM is contained within the COM+ library, **stc_mscom.dll**.

The CRM Worker is implemented via the following classes:

- XAConnection
- XAConnectionFactory
- XAQueueConnection
- XAQueueConnectionFactory
- XAQueueSession

- XARecord
- XASession
- XATopicConnection
- XATopicConnectionFactory
- XATopicSession

The CRM Compensator is implemented in the Compensator file.

When the transaction in which the CRM Worker is participating commits, the DTC calls methods contained within the CRM Compensator interface that the CRM Compensator must implement. The DTC makes these calls at each step of a two-phase commit protocol. If the prepare phase is successful, the updates are made permanent by committing the changes. If any part of the complete transaction fails, the transaction rolls back the information, aborting the transaction.

Two-phase Commit Protocol

Implementing distributed transactions is the key to the two-phase commit protocol. The activity of one or more resource managers is controlled by the transaction coordinator. There are five steps in the two-phase commit protocol.

- 1 An application invokes the commit method in the transaction coordinator.
- 2 The transaction coordinator contacts the various resource managers relevant to the transaction, and directs them to prepare to commit the transaction. (Begin phase one.)
- 3 The resource manager must be able to guarantee the ability to commit the transaction, or perform a rollback. Most resource managers write a journal file, containing the intended changes to durable storage. If unable to prepare the transaction, a negative response is set to the transaction coordinator.
- 4 All responses from the involved resource managers are collected.
- 5 The transaction coordinator informs the involved resource managers. (Phase Two) If any of resource managers responded negatively, the transaction coordinator sends a rollback command. If all of the resource managers responded affirmatively, the transaction coordinator directs all of the resource managers to commit the transaction. The transaction cannot fail after this point.

3.4.2 Implementing the Compensating Resource Manager

When planning a CRM implementation, you cannot assume that the same instance of the CRM Compensator that processes the set of method calls in the prepare phase will process the method calls in the commit phase. If one of the clients attempts to commit a transaction and the power source is inadvertently disconnected during the commit phase, the prepare method calls will not be repeated during recovery and the Compensator receives a set of abort or commit method calls.

Both the CRM Worker and Compensator are COM+ components and they must be configured using the Windows Component Services administrative tool. The CRM Worker and CRM Compensator must be installed into the same COM+ application. For

information about configuring and running the CRM samples, see [“Building the CRM Sample Application” on page 161](#).

3.4.3 Configuring the Compensating Resource Manager

To enable the CRM functionality, the Component Services must be configured using the Windows Component Services administrative tool as described in the following steps.

Step 1: Add a New Component Application on page 29

Step 2: Installing the stc_mscom Component on page 31

Step 3: Configuring the stc_mscom Component on page 33

Step 4: Configuring the STC_MSCOM.Compensator on page 34

Step 5: Configuring the STC_MSCOM XA Connection Factories on page 36

Note: Before beginning the following procedure, make sure the `stc_mscom.dll` file is registered, as described in [“Post-Installation Instructions” on page 17](#).


Step 1: Add a New Component Application

This procedure guides you through using the COM+ Application Install Wizard to create a new Component Application.

To add a new Component Application

- 1 Open the Component Services window from the Control Panel (select **Administrative Tools** and then select **Component Services**).
- 2 Expand the **Component Services** folder (see Figure 7) and right-click **COM+ Applications**.

Figure 7 Component Services Folder



- 3 On the context menu, click **New**, and then click **Application**. The COM+ Application Install Wizard opens (see Figure 8).

Figure 8 COM+ Application Install Wizard




- 4 Click **Next** to continue.
- 5 On the **Install or Create a New Application** window, click **Create an empty application** (see Figure 9).

Figure 9 COM+ Application Install Wizard



- 6 On the **Create Empty Application** window, enter the name **stc_mscom**, click the option button next to **Server application**, and then click **Next**.

Figure 10 COM+ Application Install Wizard: New Application



7 On the **Set Application Identity** page, click **Interactive User**, and then click **Next**.

Figure 11 COM+ Application Install Wizard: Set Application Identity



8 Click **Finish**.


Step 2: Installing the stc_mscom Component

Once you create the Component Application, you can install the eGate API Kit library files for COM+.

To install the stc_mscom component

- 1 From the Component Services window of the Control Panel, expand the **stc_mscom** component under **COM+ Applications** (see Figure 12).

Figure 12 Component Services: stc_mscom Component



- 2 Right-click the **Components** folder. On the shortcut menu, click **New**, and then click **Component**. The COM+ Component Install Wizard appears.
- 3 On the COM+ Component Install Wizard, click **Next**. The **Import or Install a Component** window appears.


Figure 13 COM+ Component Install Wizard



- 4 Click **Install new component(s)**. The **Select files to install** dialog appears.
- 5 In the **Select files to install** dialog, locate and select the file **stc_mscom.dll**, and then click **Open**. The **Install new components** window appears.

Note: The `stc_mscom.dll` file is located in the directory where you extracted the eGate API Kit when you installed the application (see [“Installing the eGate API Kit”](#) on page 16).

Figure 14 COM+ Component Install Wizard: Add



- 6 On the **Install new components** window, select the **Details** check box next to the **Components found** pane, and then click **Next** to continue.
- 7 Click **Finish**.


Step 3: Configuring the `stc_mscom` Component

Once you install the eGate API Kit library files, you must configure them to enable CRM.

To configure the `stc_mscom` component

- 1 Right-click the `stc_mscom` component and, on the shortcut menu, click **Properties**. The `stc_mscom Properties` dialog appears.
- 2 Click the **Advanced** tab, select the **Enable compensating resource managers** check box, and then click **OK**.

Figure 15 stc_mscom Properties: Advanced




Step 4: Configuring the STC_MSCOM.Compensator

After you configure the eGate API Kit library files, you need to configure certain components, beginning with the compensator.

To configure the STC_MSCOM.Compensator


- 1 Expand the `stc_mscom` component and click the **Components** folder.

Figure 16 STC_MSCOM.Compensator Properties




- 2 In the **Components** pane on the right side of the window, right-click **STC_MSCOM.Compensator**, and then click **Properties**.
The **STC_MSCOM.Compensator Properties** dialog appears.
- 3 Click the **Transactions** tab, and then select **Disabled** in the **Transaction support** pane.

Figure 17 STC_MSCOM.Compensator Properties: Transaction Support




- 4 Click the **Activation** tab, and then deselect the **Enable Just In Time Activation** check box.

Figure 18 STC_MSCOM.Compenstator Properties: Activation



- 5 Click the **Concurrency** tab, and then select the **Disabled** option for **Synchronization Support**.

Figure 19 STC_MSCOM.Compensator Properties: Concurrency



- 6 Click **OK**.


Step 5: Configuring the STC_MSCOM XA Connection Factories

The final step in configuring the eGate API Kit library files is to configure to XAQueueConnectionFactory component.

To configure the STC_MSCOM XA Connection Factories

- 1 In the **Components** pane, right-click **STC_MSCOM.XAQueueConnectionFactory** and then click **Properties**.
- 2 Click the **Transactions** tab, and then select the **Required** option for **Transaction support**.

Figure 20 STC_MSCOM.XAConnectionFactory Properties: Transaction Support



- 3 Click the Activation tab, and select **Enable Just In Time Activation** (this option should be already selected and might be disabled).
- 4 Click the Concurrency tab, and select the **Required** option for **Synchronization support** (this should be the only selectable option), and then click **OK**.
- 5 Repeat the above steps for the **STC_MSCOM.XATopicConnectionFactory** component.

COM+ Object Reference

The eGate API Kit provides an interface for COM+ applications to exchange data with Java CAPS Projects via the Sun SeeBeyond JMS IQ Manager. This chapter describes how to implement the Java CAPS JMS API in COM+ applications.

What's in This Chapter

- [About the Java CAPS JMS Interface for Applications in COM+](#) on page 39
- [Viewing the COM+ API](#) on page 42
- [Creating Destinations](#) on page 43
- [COM+ Constants](#) on page 43
- [BytesMessage Object](#) on page 45
- [Connection Object](#) on page 58
- [ConnectionFactory Object](#) on page 59
- [ConnectionMetaData Object](#) on page 60
- [MapMessage Object](#) on page 60
- [message Object](#) on page 73
- [MessageConsumer Object](#) on page 77
- [MessageListener Object](#) on page 78
- [MessageProducer Object](#) on page 78
- [Queue Object](#) on page 79
- [QueueBrowser Object](#) on page 80
- [QueueConnection Object](#) on page 80
- [QueueConnectionFactory Object](#) on page 82
- [QueueReceiver Object](#) on page 83
- [QueueRequestor Object](#) on page 85
- [QueueSender Object](#) on page 87
- [QueueSession Object](#) on page 89
- [session Object](#) on page 94
- [StreamMessage Object](#) on page 98
- [TemporaryQueue Object](#) on page 110

- [TemporaryTopic Object](#) on page 111
- [TextMessage Object](#) on page 113
- [Topic Object](#) on page 116
- [TopicConnection Object](#) on page 117
- [TopicConnectionFactory Object](#) on page 119
- [TopicPublisher Object](#) on page 120
- [TopicRequestor Object](#) on page 122
- [TopicSession Object](#) on page 123
- [TopicSubscriber Object](#) on page 130
- [XAQueueConnection Object](#) on page 132
- [XAQueueConnectionFactory Object](#) on page 135
- [XAQueueSession Object](#) on page 137
- [XASession Object](#) on page 141
- [XATopicConnection Object](#) on page 145
- [XATopicConnectionFactory Object](#) on page 147
- [XATopicSession Object](#) on page 150
- [Error Codes](#) on page 154


4.1 About the Java CAPS JMS Interface for Applications in COM+

This section provides information about the COM+ API for the JMS interface, including wrapper functions and mapping to the JMS API. The full COM+ API reference begins with ["BytesMessage Object" on page 45](#).

4.1.1 The COM+ Object Model

The eGate API Kit provides the `stc_mscom.dll` as its COM+ interface to access the Java CAPS JMS from COM+ applications. [Figure 21 on page 40](#) illustrates the Java CAPS JMS COM+ object model.

Figure 21 COM+ Object Model



4.1.2 Wrapper Functions for COM+ Applications

The API Kit supplies a set of JMS wrapper functions for COM+ applications to allow your applications to quickly access the Java CAPS JMS without your having to understand all JMS details.

While the wrapper functions are sufficient for most applications, they do not provide a complete function set; for details on the complete COM+ API, refer to the API descriptions in this chapter.

At a higher level of abstraction, you only need to manage a few types of structures.

- **Session**—Characterized by a hostname, port number, session type (either a pub/sub “topic session” or a point-to-point “queue session”), and connection parameters such as acknowledgment mode, transaction mode, delivery mode, and client ID.
- **Destination**—Either a topic (for pub/sub messaging) or else a queue (for point-to-point messaging). Characterized by session and destination name.
- **Message Producer**—Either a topic publisher or a queue sender. Characterized by session and destination.
- **Message Consumer**—Either a topic subscriber or a queue receiver. Characterized by session and destination (and, in pub/sub messaging only, by the name of the durable subscriber, if designated).
- **Requestor**—In request/reply messaging, either a topic requestor or a queue requestor. Characterized by session, destination, message, and time-to-live value expressed in milliseconds.
- **Message**—Characterized by the message type and payload. The payload is also called the message *body*, or message *content*.
 - ♦ For BytesMessage messages, the payload is an array of bytes.
 - ♦ For MapMessage messages, the payload is an array of name and value pairs.
 - ♦ For StreamMessage messages, the payload is a stream of primitive values.
 - ♦ For TextMessage messages, the payload is a string of text characters. Native encoding is used.

4.1.3 COM+ API Correspondence with JMS

eGate supports the Java Message Service (JMS) COM+ APIs listed in the API reference in this chapter. As much as possible, the COM+ API was designed to correspond to the standard JMS Java API. For example, the **message** and **BytesMessage** interfaces in the C++ API provide similar functionality to the JMS **Message** and **BytesMessage** interfaces. If you need additional information for each of the classes and methods, please refer to the Sun Microsystems web site at:

<http://java.sun.com/products/jms/javadoc-102a/javax/jms/package-summary.html>

This documentation provides a reference to the JMS API, and can help you understand how the COM+ methods are used in a JMS implementation.

You may also find the following books useful:

- *Java Message Service*, O'Reilly, December 2000, ISBN: 0596000685
- *Professional JMS*, Wrox Press, March 2001, ISBN: 1861004931
- *Professional Java Server Programming - J2EE Edition*, Wrox Press, September 2000, ISBN: 1861004656

Both APIs support the following features:

- Publish/subscribe, point-to-point, and request/reply messaging
- Message selectors

- Local transactions
- Distributed transactions
- Session recovery
- Temporary topics and queues
- Acknowledgement modes

Differences between the two APIs include the following.

- The COM+ API does not support the ObjectMessage interface.
- The COM+ API does not support queue browsers or connection consumers.

Table 2 lists the differences between COM+ data types and Java data types.

Table 2 COM+ Type Mapping to Java Types

COM+ Data Type	Java Data Type
currency	long
long	int
unsigned char	byte
unsigned char *	bytes[]
float	float
double	double
String	String
int	short
short	char

4.2 Viewing the COM+ API

You can view the JMS COM+ APIs using any application that is capable of viewing COM+ APIs. To view the APIs using Microsoft Visual Studio .NET, open any Visual Basic project file(.vbp) in the COM+ samples (for information about locating the sample files, see [“About the COM+ Samples” on page 157](#)).

To begin viewing the APIs

- 1 Start Microsoft Visual Basic 6.0.
- 2 In the **New Project** dialog box, click **Standard EXE** and then click **Open**.
- 3 On the **Project** toolbar, click **References**.
- 4 In the **References** dialog box, select **Sun Java Composite Application Platform Suite Message Service 5.1.0**, and then click **OK**.
- 5 On the **View** toolbar, click **Object Browser**.
- 6 From the **All Libraries** list box, select **STC_MSCOM**.

- 7 Press the F2 button to open the **Object Browser** dialog box.
- 8 From the **All Libraries** drop-down button, select **STC_MSCOM** to view the supported classes and methods.
- 9 Highlight the class to view the member methods and properties.

Note: You can also view the API in .NET by opening any of the sample projects and then viewing *stc_mscom.dll* in the Object Viewer.

4.3 Creating Destinations

Destinations do not need to be created separately: they are created through the `session.createQueue()` and `session.createTopic()` functions. If these destinations do not exist, they are created automatically.

4.4 COM+ Constants

The COM+ API for SeeBeyond JMS defines values for the following types of constants:

- [AcknowledgeMode Constants](#) on page 43
- [DeliveryMode Constants](#) on page 44
- [Message Constants](#) on page 44
- [Priority Constants](#) on page 45

For a list of error code constants, see [“Error Value Constants” on page 155](#).

4.4.1 AcknowledgeMode Constants

Table 3 lists the acknowledgement modes along with their corresponding integer values.

Table 3 Values for AcknowledgeMode Constants

Name	Value	Description
msAutoAcknowledge	1	1 indicates auto-acknowledgment. The session automatically acknowledges a client’s receipt of a message either upon its successful return from a call to receive or upon successful return of the MessageListener it has called to process the message.

Table 3 Values for AcknowledgeMode Constants

Name	Value	Description
msClientAcknowledge	2	2 indicates acknowledgment by client. A client acknowledges a message by calling the message's acknowledge method. Acknowledging a consumed message automatically acknowledges the receipt of all messages that have been delivered by its session.
msDupsOkAcknowledge	3	3 indicates that duplicates are acceptable, and instructs the session to lazily acknowledge message delivery. This setting is likely to cause delivery of some duplicate messages if JMS fails, and should only be used by consumers that are tolerant of duplicate messages. The benefit is the reduction of session overhead, achieved by minimizing the work done to prevent duplicates.

4.4.2 DeliveryMode Constants

Table 4 lists the delivery mode constants and their corresponding integer values.

Table 4 Values for DeliveryMode Constants

Name	Value	Description
msNonPersistent	0	0 indicates non-persistent delivery mode. This is the lowest overhead delivery mode because it does not require the message to be logged to storage. The JMS IQ Manager delivers a nonpersistent message with a one-time-only delivery. If the JMS IQ Manager goes down, the message is lost. This mode maximizes performance and should be used if an occasional lost message is tolerable.
msPersistent	1	1 indicates persistent delivery mode. This mode instructs the JMS IQ Manager to log the message to storage as part of the client's send operation. It maximizes reliability and should be used if the application will have problems if the message is lost in transit.

4.4.3 Message Constants

Table 5 lists the default values for the message delivery mode, priority, and expiration period.

Table 5 Values for Message Constants

Name	Value	Description
msDefaultDeliveryMode	1	See DeliveryMode Constants on page 44.
msDefaultPriority	4	JMS defines a ten-level priority value: 0 is lowest priority (least expedited) and 9 is highest. Clients should consider priorities 0 through 4 as gradations of normal priority and priorities 5 through 9 as gradations of expedited priority.
msDefaultTimeToLive	0	Length of time that a produced message should be retained by the message system. Measured in milliseconds elapsed since its dispatch time. The default, 0 , has the special meaning of “retain forever” – that is, the message never expires on its own.

4.4.4 Priority Constants

Priority constants define a ten-level priority system for messages (see “msDefaultPriority” in Table 5). Table 6 lists the priority constants and their corresponding integer values.

Table 6 Priority Level Constants

Name	Value
msPriorityEight	8
msPriorityFive	5
msPriorityFour	4
msPriorityNine	9
msPriorityOne	1
msPrioritySeven	7
msPrioritySix	6
msPriorityThree	3
msPriorityTwo	2
msPriorityZero	0

4.5 BytesMessage Object

A **BytesMessage** is used to send a message containing a stream of uninterrupted bytes. It inherits **message** and adds a bytes message body. The receiver of the message supplies the interpretation of the bytes. The **BytesMessage** object is a member of the **message** object.

4.5.1 BytesMessage Properties

The **BytesMessage** object includes the properties listed in Table 7.

Table 7 Properties of the BytesMessage Object

Property	Data Type	Description
CorrelationID	String	Sets or returns correlation ID values that are either JMS IQ Manager message IDs or application-specific strings.
CorrelationIDAsBytes	Variant	This is not currently supported.
DeliveryMode	BytesMessageConstant	Sets or returns the delivery mode for this message as either <code>msNonPersistent</code> , or <code>msPersistent</code> . The default value is <code>msDefaultDeliveryMode</code> (<code>msPersistent</code>). See DeliveryMode Constants on page 44.
Destination	Destination	This is not currently supported.
Expiration	Currency	Sets or returns the message expiration time in milliseconds.
MessageID	String	Sets or returns the value of the uniquely assigned identifier in the message header.
Priority	PriorityConstants	This is not currently supported.
Redelivered	Boolean	Sets or returns an indicator of whether the message is redelivered. A value of true indicates the message is redelivered; a value of false indicates it is not.
ReplyTo	Destination	Sets or returns the destination to which a reply to the message is sent. A destination can be a Topic, Queue, Temporary Topic, or a Temporary Queue.
Timestamp	Currency	Sets or returns the timestamp of the message.
Type	String	Sets or returns the message type.

4.5.2 BytesMessage Methods

The **BytesMessage** object includes the following methods:

- [Acknowledge](#) on page 47
- [ClearBody](#) on page 47
- [ClearProperties](#) on page 48
- [GetProperty](#) on page 48
- [ReadUnsignedShort](#) on page 52
- [ReadUTF](#) on page 53
- [Reset](#) on page 53
- [SetProperty](#) on page 54

- [PropertyExists](#) on page 48
- [ReadBoolean](#) on page 49
- [ReadByte](#) on page 49
- [ReadBytes](#) on page 50
- [ReadChar](#) on page 50
- [ReadDouble](#) on page 50
- [ReadFloat](#) on page 51
- [ReadInt](#) on page 51
- [ReadLong](#) on page 51
- [ReadShort](#) on page 52
- [ReadUnsignedByte](#) on page 52
- [WriteBoolean](#) on page 54
- [WriteByte](#) on page 54
- [WriteBytes](#) on page 55
- [WriteChar](#) on page 55
- [WriteDouble](#) on page 56
- [WriteFloat](#) on page 56
- [WriteInt](#) on page 56
- [WriteLong](#) on page 57
- [WriteObject](#) on page 57
- [WriteShort](#) on page 57
- [WriteUTF](#) on page 58

Acknowledge

Syntax

```
Sub Acknowledge()
```

Description

Acknowledges the receipt of current and previous messages.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ClearBody

Syntax

```
Sub ClearBody()
```

Description

Clears the body of a message, leaving the message header values and property entries intact.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ClearProperties

Syntax

```
Sub ClearProperties()
```

Description

Clears the properties from a message, leaving the message header fields and body intact.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

GetProperty

Syntax

```
Function GetProperty(name As String)
```

Description

Returns the Visual Basic data type property value with the given name into the message.

Parameters

Name	Type	Description
name	String	The name of the property.

Return Value

The value of the specified property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

PropertyExists

Syntax

```
Function PropertyExists(name As String) As Boolean
```

Description

Checks whether a value for a specific property exists.

Parameters

Name	Type	Description
name	String	The name of the property to check.

Return Value

A Boolean indicator of whether a value exists for the specified property. If the property value exists, the return value is **true**; otherwise, it is **false**.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadBoolean

Syntax

```
Function ReadBoolean() As Boolean
```

Description

Reads a Boolean value from the bytes message stream.

Parameters

None.

Return Value

The value of the Boolean property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadByte

Syntax

```
Function ReadByte() As Byte
```

Description

Reads a signed 8-bit value from the bytes message stream.

Parameters

None.

Return Value

The value of the Byte property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadBytes

Syntax

```
Function ReadBytes(value, [length]) As Long
```

Description

Reads a portion of the bytes message stream.

Parameters

Name	Type	Description
value	Variant	The buffer into which the data is read.
length	Variant	The number of bytes to read.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadChar

Syntax

```
Function ReadChar() As Short
```

Description

Reads a Unicode character value from the bytes message stream.

Parameter

None.

Return Value

The value of the character.

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadDouble

Syntax

```
Function ReadDouble() As Double
```

Description

Reads a double value from the bytes message stream.

Parameters

None.

Return Value

The value of the double property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadFloat

Syntax

```
Function ReadFloat() As Single
```

Description

Reads a floating point value from the bytes message stream.

Parameters

None.

Return Value

The value of the floating point property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadInt

Syntax

```
Function ReadInt() As Long
```

Description

Reads a signed 32-bit integer value from the bytes message stream.

Parameters

None.

Return Value

The value of the integer property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadLong

Syntax

```
Function ReadLong() As Currency
```

Description

Reads a signed 64-bit integer value from the bytes message stream.

Parameters

None.

Return Value

The value of the long property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadShort

Syntax

```
Function ReadShort() As Integer
```

Description

Reads a signed 16-bit number from the bytes message stream.

Parameters

None.

Return Value

The value of the short property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadUnsignedByte

Syntax

```
Function ReadUnsignedByte() As Long
```

Description

Reads an unsigned 8-bit number from the bytes message stream.

Parameters

None.

Return Value

The value of the unsigned byte property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadUnsignedShort

Syntax

```
Function ReadUnsignedShort() As Long
```

Description

Reads an unsigned 16-bit number from the bytes message stream.

Parameters

None.

Return Value

The value of the unsigned short property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadUTF

Syntax

```
Function ReadUTF() As String
```

Description

Reads a string that was encoded using a modified UTF-8 format from the bytes message stream.

Parameters

None.

Return Value

A String containing the value of the UTF-encoded property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Reset

Syntax

```
Sub Reset()
```

Description

Places the message body in read-only mode and repositions the stream of bytes to the beginning.

Parameters

None.

Return Value

None.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

SetProperty

Syntax

```
Sub SetProperty(name As String, value)
```

Description

Sets a Visual Basic data type value into the message property with the specified name.

Parameters

Name	Type	Description
name	String	The name of the property.
value	Variant	The value to set in the specified property.

Return Value

None.

WriteBoolean

Syntax

```
Sub WriteBoolean(value As Boolean)
```

Description

Writes a Boolean value to the bytes message stream as a 1-byte value.

Parameters

Name	Type	Description
value	Boolean	The value to write. The value true is written out as the value (byte)1; the value false is written out as the value (byte)0.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteByte

Syntax

```
Sub WriteByte(value As Byte)
```

Description

Writes a 1-byte value to the bytes message stream.

Parameters

Name	Type	Description
value	Byte	The value to write.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteBytes

Syntax

```
Sub WriteBytes(value, [offset], [length])
```

Description

Writes a byte array, or a portion of the byte array, to the bytes message stream.

Parameters

Name	Type	Description
value	Variant	The byte array value to write.
offset	Variant	The initial offset within the byte array.
length	Variant	The number of bytes to use.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteChar

Syntax

```
Sub WriteChar(value As Short)
```

Description

Writes a char value to the bytes message stream as a 2-byte value, high byte first.

Parameters

Name	Type	Description
value	Short	The value to write.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteDouble

Syntax

```
Sub WriteDouble(value As Double)
```

Description

Converts the double parameter value to a long value, and then writes an 8-byte long value to the bytes message stream (high byte is written first).

Parameters

Name	Type	Description
value	Double	The value to write.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteFloat

Syntax

```
Sub WriteFloat(Value As Single)
```

Description

Converts the floating point argument to a long value, and then writes a 4-byte long value to the bytes message stream (high byte is written first).

Parameters

Name	Type	Description
value	Single	The value to write.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteInt

Syntax

```
Sub WriteInt(value As Long)
```

Description

Writes a number to the bytes message stream as a 4-byte integer (high byte is written first).

Parameters

Name	Type	Description
value	Long	The value to write.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteLong

Syntax

```
Sub WriteLong(value As Currency)
```

Description

Writes a number to the bytes message stream as an 8-byte long value (high byte is written first).

Parameters

Name	Type	Description
value	Currency	The value to write.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteObject

This method is not currently supported.

WriteShort

Syntax

```
Sub WriteShort(value As Integer)
```

Description

Writes a number to the bytes message stream as a 2-byte short integer (high byte is written first).

Parameters

Name	Type	Description
value	Integer	The value to write.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteUTF

Syntax

```
Sub WriteUTF(value As String)
```

Description

Writes a string to the bytes message stream using UTF-8 encoding in a machine-independent manner.

Parameters

Name	Type	Description
value	String	The value to write.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.6 Connection Object

A **Connection** is a client's active connection to its provider. This is an abstract interface.

4.6.1 Connection Properties

The **Connection** object includes the properties listed in Table 8.

Table 8 Properties of the Connection Object

Property	Data Type	Description
ClientID	String	Sets or returns the client identifier for this connection. This value is specified to the JMS IQ Manager.
MetaData	ConnectionMetaData	This is not currently supported.

4.6.2 Connection Methods

The **Connection** object includes the following methods:

- **Start** on page 59
- **Stop** on page 59

Start

Syntax

```
Sub Start()
```

Description

Starts or restarts the delivery of a transaction connection's incoming messages.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Stop

Syntax

```
Sub Stop()
```

Description

Temporarily stops the delivery of incoming messages from a transaction connection.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.7 ConnectionFactory Object

A **ConnectionFactory** encapsulates a set of connection configuration parameters that is defined by the administrator. This is an abstract interface.

There are no methods associated with this object.

4.7.1 ConnectionFactory Properties

The **ConnectionFactory** object includes the properties listed in Table 9.

Table 9 Properties of the ConnectionFactory Object

Property	Data Type	Description
HostName	String	Sets or returns the name of the host where the message service is running.

Table 9 Properties of the ConnectionFactory Object

Property	Data Type	Description
Port	Long	Sets or returns the port number at which the message service is listening. The default value is 24053 .
PortOffset	Long	Sets or returns the port offset number of the message service if more then one service is running on the same host machine and using the same port number.

4.8 ConnectionMetaData Object

This object is currently not supported.

4.9 MapMessage Object

The **MapMessage** object is used to send a set of name-value pairs where names are Strings and values are primitive data types. The **MapMessage** object is a member of the **message** object.

4.9.1 MapMessage Properties

The **MapMessage** object includes the properties listed in Table 10.

Table 10 Properties of the MapMessage Object

Property	Data Type	Description
CorrelationID	String	Sets or returns correlation ID values that are either JMS IQ Manager message IDs or application-specific strings.
CorrelationIDAsBytes	Variant	This is not currently supported.
DeliveryMode	DeliveryModeConstant	Sets or returns the delivery mode for this message as either <code>msNonPersistent</code> , or <code>msPersistent</code> . The default value is <code>msDefaultDeliveryMode (msPersistent)</code> . See DeliveryMode Constants on page 44.
Destination	Destination	This is not currently supported.
Expiration	Currency	Sets or returns the message expiration time in milliseconds.

Table 10 Properties of the MapMessage Object

Property	Data Type	Description
MapNames	Variant	Returns the map message names as an array of Strings. This property is read-only.
MessageID	String	Sets or returns the value of the uniquely assigned identifier in the message header.
Priority	PriorityConstants	This is not currently supported.
Redelivered	Boolean	Sets or returns an indicator of whether the message is redelivered. A value of true indicates the message is redelivered; a value of false indicates it is not.
ReplyTo	Destination	Sets or returns the destination to which a reply to the message is sent. A destination can be a Topic, Queue, TemporaryTopic, or a TemporaryQueue.
Timestamp	Currency	Sets or returns the message timestamp.
Type	String	Sets or returns the message type.

4.9.2 MapMessage Object Methods

The **MapMessage** object includes the following methods:

- **Acknowledge** on page 62
- **ClearBody** on page 62
- **ClearProperties** on page 62
- **GetBoolean** on page 63
- **GetByte** on page 63
- **GetBytes** on page 63
- **GetChar** on page 64
- **GetDouble** on page 64
- **GetFloat** on page 65
- **GetInt** on page 65
- **GetLong** on page 66
- **GetObject** on page 66
- **GetProperty** on page 66
- **GetShort** on page 67
- **GetString** on page 67
- **ItemExists** on page 67
- **PropertyExists** on page 68
- **SetBoolean** on page 68
- **SetByte** on page 69
- **SetBytes** on page 69
- **SetChar** on page 70
- **SetDouble** on page 70
- **SetFloat** on page 70
- **SetInt** on page 71
- **SetLong** on page 71
- **SetObject** on page 72
- **SetProperty** on page 72
- **SetShort** on page 72
- **SetString** on page 73

Acknowledge

Syntax

```
Sub Acknowledge()
```

Description

Acknowledges the receipt of current and previous messages.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ClearBody

Syntax

```
Sub ClearBody()
```

Description

Clears the body of a message, leaving the message header values and property entries intact.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ClearProperties

Syntax

```
Sub ClearProperties()
```

Description

Clears the properties from a message, leaving the message header fields and body intact.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

GetBoolean

Syntax

```
Function GetBoolean(name As String) As Boolean
```

Description

Retrieves the value of the specified Boolean property.

Parameters

Name	Type	Description
name	String	The name of the property to check.

Return Value

The value of the Boolean property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

GetByte

Syntax

```
Function GetByte(name As String) As Byte
```

Description

Retrieves the value of the specified byte property.

Parameters

Name	Type	Description
name	String	The name of the property to check.

Return Value

The value of the byte property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

GetBytes

Syntax

```
Function GetBytes(name As String, length As Long)
```

Description

Retrieves a byte array value from the specified byte property.

Parameters

Name	Type	Description
name	String	The name of the property to check.
length	Long	The number of bytes to retrieve.

Return Value

A byte array value from the byte property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

GetChar

Syntax

```
Function GetChar(name As String) As Short
```

Description

Retrieves the Unicode character value of the specified property.

Parameters

Name	Type	Description
name	String	The name of the property to check.

Return Value

The value of the specified property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

GetDouble

Syntax

```
Function GetDouble(name As String) As Double
```

Description

Retrieves the value of the specified double property.

Parameters

Name	Type	Description
name	String	The name of the property to check.

Return Value

The value of the double property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

GetFloat

Syntax

```
Function GetFloat(name As String) As Single
```

Description

Retrieves the Single value of the specified floating point property.

Parameters

Name	Type	Description
name	String	The name of the property to check.

Return Value

The value of the floating point property as a Single value.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

GetInt

Syntax

```
Function GetInt(name as a String) As Long
```

Description

Retrieves the long value of the specified integer property.

Parameters

Name	Type	Description
name	String	The name of the property to check.

Return Value

The value of the integer property as a Long value.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

GetLong

Syntax

```
Function GetLong(name As String) As Currency
```

Description

Retrieves the Currency value of the specified long property.

Parameters

Name	Type	Description
name	String	The name of the property to check.

Return Value

The value of the long property as a Currency value.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

GetObject

This method is not currently supported.

GetProperty

Syntax

```
Function GetProperty(name As String)
```

Description

Retrieves the Visual Basic data type property value with the given name into the MapMessage.

Parameters

Name	Type	Description
name	String	The name of the property to check.

Return Value

The value of the specified property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

GetShort

Syntax

```
Function GetShort(name As String) As Integer
```

Description

Retrieves the Integer value of the specified short property.

Parameters

Name	Type	Description
name	String	The name of the property to check.

Return Value

The value of the short property as an Integer value.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

GetString

Syntax

```
Function GetString(name As String) As String
```

Description

Retrieves the value of the specified String property.

Parameters

Name	Type	Description
name	String	The name of the property to check.

Return Value

The value of the String property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ItemExists

Syntax

```
Function ItemExists(name As String) As Boolean
```

Description

Checks whether the specified item exists in the MapMessage.

Parameters

Name	Type	Description
name	String	The name of the item to check.

Return Value

A Boolean indicator of whether the item exists. If the item exists, the return value is **true**; otherwise it is **false**.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

PropertyExists

Syntax

```
Function PropertyExists (name As String) As Boolean
```

Description

Checks whether a value for the specified property exists.

Parameters

Name	Type	Description
name	String	The name of the property to check.

Return Value

A Boolean indicator of whether the property value exists. If the value exists, the return value is **true**; otherwise it is **false**.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

SetBoolean

Syntax

```
Sub SetBoolean (name As String, value As Boolean)
```

Description

Sets a Boolean property value with the specified name into the MapMessage.

Parameters

Name	Type	Description
name	String	The name of the property to update.
value	Boolean	The Boolean value to set.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

SetByte

Syntax

```
Sub SetByte(name As String, value As Byte)
```

Description

Sets a byte property value with the specified name into the MapMessage.

Parameters

Name	Type	Description
name	String	The name of the property to update.
value	Byte	The byte value to set.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

SetBytes

Syntax

```
Sub SetBytes(name As String, value, [offset], [length])
```

Description

Sets a byte array or a portion of the value with the specified name into the MapMessage.

Parameters

Name	Type	Description
name	String	The name of the property to update.
value	Variant	The value to set.
offset	Variant	The initial offset within the byte array.
length	Variant	The number of bytes to use.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

SetChar

Syntax

```
Sub SetChar(name As String, value As Short)
```

Description

Sets a Unicode character value with the specified name into the MapMessage.

Parameters

Name	Type	Description
name	String	The name of the property to update.
value	Short	The value to set.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

SetDouble

Syntax

```
Sub SetDouble(name As String, value As Double)
```

Description

Sets a double property value with the specified name into the MapMessage.

Parameters

Name	Type	Description
name	String	The name of the property to update.
value	Double	The Double value to set.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

SetFloat

Syntax

```
Sub SetFloat(name As String, value As Single)
```

Description

Sets a floating point property value with the specified name into the MapMessage.

Parameters

Name	Type	Description
name	String	The name of the property to update.
value	Single	The floating point value to set.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

SetInt

Syntax

```
Sub SetInt(name As String, value As Long)
```

Description

Sets an integer property value with the specified name into the MapMessage.

Parameters

Name	Type	Description
name	String	The name of the property to update.
value	Long	The value to set.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

SetLong

Syntax

```
Sub SetLong(name As String, value As Currency)
```

Description

Sets a long property value with the specified name into the MapMessage.

Parameters

Name	Type	Description
name	String	The name of the property to update.
value	Currency	The long value to set.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

SetObject

This method is not currently supported.

SetProperty

Syntax

```
Sub SetProperty(name As String, value)
```

Description

Sets a Visual Basic data type property value with the specified name into the MapMessage.

Parameters

Name	Type	Description
name	String	The name of the property to update.
value	Variant	The value to set.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

SetShort

Syntax

```
Sub SetShort(name As String, value As Integer)
```

Description

Sets a short property value with the specified name into the MapMessage.

Parameters

Name	Type	Description
name	String	The name of the property to update.
value	Integer	The value to set.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

SetString

Syntax

```
Sub SetString(name As String, value As String)
```

Description

Sets a String property value with the specified name into the MapMessage.

Parameters

Name	Type	Description
name	String	The name of the property to update.
value	String	The String value to set.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.10 message Object

The **message** interface is the root interface of all JMS messages. It defines the JMS header and the acknowledge method used for all messages. Subclasses of the **message** object include: **BytesMessage**, **MapMessage**, **TextMessage**, and **StreamMessage**.

4.10.1 message Properties

The **message** object includes the properties listed in Table 11.

Table 11 Properties of the message Object

Property	Data Type	Description
CorrelationID	String	Sets or returns correlation ID values that are either JMS IQ Manager message IDs or application-specific strings.
CorrelationIDAsBytes	Variant	This is not currently supported.
DeliveryMode	DeliveryModeConstant	Sets or returns the delivery mode for this message as either msNonPersistent, or msPersistent. The default value is msDefaultDeliveryMode (msPersistent). See DeliveryMode Constants on page 44.
Destination	Destination	This is not currently supported.
Expiration	Currency	Sets or returns the message expiration time in milliseconds.

Table 11 Properties of the message Object

Property	Data Type	Description
MessageID	String	Sets or returns the value of the uniquely assigned identifier in the message header.
Priority	PriorityConstants	This is not currently supported.
Redelivered	Boolean	Sets or returns an indicator of whether the message is redelivered. A value of true indicates the message is redelivered; a value of false indicates it is not.
ReplyTo	Destination	Sets or returns the destination to which a reply to the message is sent. A destination can be a Topic, Queue, TemporaryTopic, or a TemporaryQueue.
Timestamp	Currency	Sets or returns the message timestamp.
Type	String	Sets or returns the message type.

4.10.2 message Methods

The **message** object includes the following methods:

- [Acknowledge](#) on page 74
- [ClearBody](#) on page 75
- [ClearProperties](#) on page 75
- [GetProperty](#) on page 75
- [PropertyExists](#) on page 76
- [SetProperty Method](#) on page 76

Acknowledge

Syntax

```
Sub Acknowledge()
```

Description

Acknowledges the receipt of current and previous messages.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ClearBody

Syntax

```
Sub ClearBody()
```

Description

Clears the body of a message, leaving the message header values and property entries intact.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ClearProperties

Syntax

```
Sub ClearProperties()
```

Description

Clears the properties from a message, leaving the message header fields and body intact.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

GetProperty

Syntax

```
Function GetProperty(name As String)
```

Description

Retrieves the Visual Basic data type property value with the given name into the message.

Parameters

Name	Type	Description
name	String	The name of the property to check.

Return Value

The value of the specified property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

PropertyExists

Syntax

```
Function PropertyExists (name As String) As Boolean
```

Description

Checks whether a value for the specified property exists.

Parameters

Name	Type	Description
name	String	The name of the property to check.

Return Value

A Boolean indicator of whether the property value exists. If the value exists, the return value is **true**; otherwise it is **false**.

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

SetProperty Method

Syntax

```
Sub SetProperty(name As String, value)
```

Description

Sets a Visual Basic data type value into the message property with the specified name.

Parameters

Name	Type	Description
name	String	The name of the property.
value	Variant	The value to set in the specified property.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.11 MessageConsumer Object

The **MessageConsumer** receives messages from a destination. This is an abstract interface.

4.11.1 MessageConsumer Properties

The **MessageConsumer** object includes the properties listed in Table 12.

Table 12 Properties of the MessageConsumer Object

Property	Data Type	Description
MessageListener	MessageListener	This is not currently supported.
MessageSelector	String	Returns the message consumer's selector expression.

4.11.2 MessageConsumer Methods

The **MessageConsumer** object includes the following methods:

- **Close** on page 77
- **ReceiveMessage** on page 77
- **ReceiveNoWait** on page 78

Close

Syntax

```
Sub Close()
```

Description

Closes resources on behalf of a message consumer. A message service can allocate resources on behalf of a message consumer, so it is recommended that you close any unused resources.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReceiveMessage

Syntax

```
Function Receive([timeOut]) As message
```

Description

Receives the next message produced or the next message that arrives within the specified timeout interval for the message consumer.

Parameters

Name	Type	Description
timeOut	Variant	The timeout value of the message consumer in milliseconds.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReceiveNoWait

Syntax

```
Function ReceiveNoWait() As message
```

Description

Receives the next message if one is immediately available.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.12 MessageListener Object

This object is not currently supported.

4.13 MessageProducer Object

The **MessageProducer** sends messages to a destination. Sub interfaces of the **MessageProducer** object include **QueueSender** and **TopicPublisher**. This is an abstract interface.

There are no methods associated with this object.

4.13.1 MessageProducer Properties

The **MessageProducer** object includes the properties listed in Table 13.

Table 13 Properties of the MessageProducer Object

Property	Data Type	Description
DeliveryMode	DeliveryModeConstant	Sets or returns the delivery mode for this message as either <code>msNonPersistent</code> , or <code>msPersistent</code> . The default value is <code>msDefaultDeliveryMode</code> (<code>msPersistent</code>). See DeliveryMode Constants on page 44.
DisableMessageID	Boolean	Sets or returns an indicator of whether message IDs are disabled. A value of true indicates message IDs are disabled; false indicates they are not.
DisableMessageTimestamp	Boolean	Sets or returns an indicator of whether timestamping is disabled. A value of true indicates timestamping is disabled; false indicates it is not.
Priority	PriorityConstants	This is not currently supported.
TimeToLive	Currency	Sets or returns the default length of time in milliseconds from its dispatch time that a produced message should be retained by the message system. The default value is <code>msDefaultTimeToLive</code> (0 (zero), which is unlimited).

4.14 Queue Object

A **Queue** object encapsulates a message service-specific queue name.

4.14.1 Queue Properties

The **Queue** object includes the property listed in Table 14.

Table 14 Properties of the Queue Object

Property	Data Type	Description
QueueName	String	Returns the name of this queue. This property is read-only.

4.14.2 Queue Methods

The **Queue** object includes the following method:

- **ToString** on page 80

ToString

Syntax

```
Function ToString() As String
```

Description

Retrieves a printed version of the queue name.

Parameters

None.

Return Value

The queue name as a String.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.15 QueueBrowser Object

This object is currently not supported.

4.16 QueueConnection Object

A **QueueConnection** is an active connection to a point-to-point message service.

4.16.1 QueueConnection Properties

The **QueueConnection** object includes the properties listed in Table 15.

Table 15 Properties of the QueueConnection Object

Property	Data Type	Description
ClientID	String	Sets or returns the client identifier for the connection.
MetaData	ConnectionMetaData	This is not currently supported.

4.16.2 QueueConnection Methods

The **QueueConnection** object includes the following methods:

- [CreateQueueSession](#) on page 81
- [Start](#) on page 81
- [Stop](#) on page 82

CreateQueueSession

Syntax

```
Function CreateQueueSession(Transacted As Boolean, acknowledgeMode As AcknowledgeModeConstants) As QueueSession
```

Description

Creates a **QueueSession** using the specified transacted and acknowledge modes.

Parameters

Name	Type	Description
Transacted	Boolean	An indicator of the whether the session is transacted. A value of true indicates the session is transacted; false means it is not.
acknowledgeMode	AcknowledgeModeConstants	An indicator of the acknowledgement mode. See AcknowledgeMode Constants on page 43 for possible values.

Return Value

A queue session.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Start

Syntax

```
Sub Start()
```

Description

Starts or restarts a connection's delivery of incoming messages.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Stop

Syntax

```
Sub Stop()
```

Description

Temporarily stops a connection's delivery of incoming messages.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.17 QueueConnectionFactory Object

A client uses a **QueueConnectionFactory** to create queue connections (**QueueConnection**) for a point-to-point message service.

4.17.1 QueueConnectionFactory Properties

The **QueueConnectionFactory** object includes the properties listed in Table 16.

Table 16 Properties of the QueueConnectionFactory Object

Property	Data Type	Description
HostName	String	Sets or returns the name of the host where the message service is running.
Port	Long	Sets or returns the port number at which the message service is listening. The default value is 24053 .
PortOffset	Long	Sets or returns the port offset number of the message service if more than one service is running on the same host machine and using the same port number.

4.17.2 QueueConnectionFactory Methods

The **QueueConnectionFactory** object includes the following methods:

- [CreateQueueConnection](#) on page 83
- [CreateQueueConnectionEx](#) on page 83

CreateQueueConnection

Syntax

```
Function CreateQueueConnection() As QueueConnection
```

Description

Creates a queue connection with a default user identity.

Parameters

None.

Return Value

A queue connection.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateQueueConnectionEx

Syntax

```
Function CreateQueueConnection(userId As String, password As String)  
As QueueConnection
```

Description

Creates a queue connection with the specified user identity.

Parameters

Name	Type	Description
userId	String	The logon user ID.
password	String	The password associated with the specified user ID.

Return Value

A queue connection.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.18 QueueReceiver Object

A client uses a **QueueReceiver** for receiving messages that have been delivered to a queue.

4.18.1 QueueReceiver Properties

The **QueueReceiver** object includes the properties listed in Table 17.

Table 17 Properties of the QueueReceiver Object

Property	Data Type	Description
MessageListener	MessageListener	This is not currently supported.
MessageSelector	String	Returns the message selector expression for the message consumer. This property is read-only.
Queue	Queue	Returns the queue associated with the queue receiver.

4.18.2 QueueReceiver Methods

The **QueueReceiver** object includes the following methods:

- **Close** on page 84
- **Receive** on page 84
- **ReceiveNoWait** on page 85

Close

Syntax

```
Sub Close()
```

Description

Closes the queue receiver. A message service might allocate resources on behalf of a message consumer, so the receiver should be closed when it is no longer needed.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Receive

Syntax

```
Function Receive([timeOut]) As message
```

Description

Receives the next message produced or the next message that arrives within the specified timeout interval for this message consumer

Parameters

Name	Type	Description
timeOut	Variant	The timeout value for the message consumer in milliseconds.

Return Value

A **message** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReceiveNoWait

Syntax

```
Function ReceiveNoWait() As message
```

Description

Receives the next message if one is immediately available.

Parameters

None

Return Value

A **message** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.19 QueueRequestor Object

The **QueueRequestor** object provides a helper class to simplify making service requests.

4.19.1 QueueRequestor Methods

The **QueueRequestor** object includes the following methods:

- [Close](#) on page 86
- [Create](#) on page 86
- [Request](#) on page 86

Close

Syntax

```
Sub Close()
```

Description

Closes the queue requestor.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Create

Syntax

```
Sub Create(session As QueueSession, Queue As Queue)
```

Description

Creates a queue requestor.

Parameters

Name	Type	Description
session	QueueSession	The queue session.
Queue	Queue	The queue associated with the queue requestor.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Request

Syntax

```
Function Request(message As message, [timeOut]) As message
```

Description

Sends a request to the queue and waits for a reply, optionally for a specified amount of time.

Parameters

Name	Type	Description
message	message	The message to send.
timeOut	Variant	The timeout value for the message in milliseconds.

Return Value

A reply message.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.20 QueueSender Object

A client uses a **QueueSender** to send messages to a queue.

4.20.1 QueueSender Properties

The **QueueSender** object includes the properties listed in Table 18.

Table 18 Properties of the QueueSender Object

Property	Data Type	Description
DeliveryMode	DeliveryModeConstants	Sets or returns the delivery mode for this message as either <code>msNonPersistent</code> , or <code>msPersistent</code> . The default value is <code>msDefaultDeliveryMode</code> (<code>msPersistent</code>). See DeliveryMode Constants on page 44.
DisableMessageID	Boolean	Sets or returns an indicator of whether message IDs are disabled. A value of true indicates message IDs are disabled; false indicates they are not.
DisableMessageTimestamp	Boolean	Sets or returns an indicator of whether timestamping is disabled. A value of true indicates timestamping is disabled; false indicates it is not.
Priority	PriorityConstants	This is not currently supported.
Queue	Queue	Returns the queue associated with the queue sender. This property is read-only.

Table 18 Properties of the QueueSender Object

Property	Data Type	Description
TimeToLive	Currency	Sets or returns the default length of time in milliseconds from its dispatch time that a produced message should be retained by the message system. The default value is msDefaultTimeToLive (0 (zero), which is unlimited).

4.20.2 QueueSender Methods

The **QueueSender** object includes the following method:

- [Send](#) on page 88

Send

Syntax

```
Sub Send(message As message, [DeliveryMode], [Priority], [TimeToLive], [Queue])
```

Description

Sends a message to a queue for an unidentified message producer, specifying delivery mode, priority, time to live, and receiving queue.

Parameters

Name	Type	Description
message	message	The message to send.
DeliveryMode	Variant	The delivery mode for the message. See DeliveryMode Constants on page 44.
Priority	Variant	The priority for the message (not currently supported).
TimeToLive	Variant	The lifetime of the message in milliseconds.
Queue	Variant	The queue to which the message should be sent.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.21 QueueSession Object

A **QueueSession** provides methods for creating the following objects: **QueueReceiver**, **QueueSender**, **QueueBrowser**, and **TemporaryQueue**.

4.21.1 QueueSession Properties

The **QueueSession** object includes the properties listed in Table 19.

Table 19 Properties of the QueueSession Object

Property	Data Type	Description
MessageListener	MessageListener	This is not currently supported.
Transacted	Boolean	Returns an indicator of whether the session is in transacted mode. A value of true indicates the session is in transacted mode; a value of false indicates it is not. This property is read-only.

4.21.2 QueueSession Object Methods

The **QueueSession** object includes the following methods:

- [Commit](#) on page 89
- [CreateBytesMessage](#) on page 90
- [CreateMapMessage](#) on page 90
- [CreateMessage](#) on page 90
- [CreateQueue](#) on page 91
- [CreateReceiver](#) on page 91
- [CreateSender](#) on page 92
- [CreateStreamMessage](#) on page 92
- [CreateTemporaryQueue](#) on page 92
- [CreateTextMessage](#) on page 93
- [Recover](#) on page 93
- [Rollback](#) on page 93
- [Run](#) on page 94

Commit

Syntax

```
Sub Commit()
```

Description

Commits all messages processed in this transaction and releases any locks currently held.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateBytesMessage

Syntax

```
Function CreateBytesMessage() As BytesMessage
```

Description

Creates a **BytesMessage** object (see [“BytesMessage Object” on page 45](#)).

Parameters

None.

Return Value

A **BytesMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateMapMessage

Syntax

```
Function CreateMapMessage() As MapMessage
```

Description

Creates a **MapMessage** object (see [“MapMessage Object” on page 60](#)).

Parameters

None.

Return Value

A **MapMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateMessage

Syntax

```
Function CreateMessage() As message
```

Description

Creates a **message** object (see [“message Object” on page 73](#)).

Parameters

None.

Return Value

A **message** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateQueue

Syntax

```
Function CreateQueue(QueueName As String) As Queue
```

Description

Creates a queue identity given a queue name.

Parameters

Name	Type	Description
QueueName	String	The name of the queue to create.

Return Value

A **Queue** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateReceiver

Syntax

```
Function CreateReceiver(Queue As Queue, [MessageSelector]) As  
QueueReceiver
```

Description

Creates a **QueueReceiver** to receive messages for the specified queue.

Parameters

Name	Type	Description
Queue	Queue	The queue to access.
MessageSelector	Variant	The message selector expression that a message's properties must match in order to be delivered.

Return Value

A **QueueReceiver** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateSender

Syntax

```
Function CreateSender(Queue As Queue) As QueueSender
```

Description

Creates a **QueueSender** to send messages to the specified queue.

Parameters

Name	Type	Description
Queue	Queue	The queue to which the messages will be sent.

Return Value

A **QueueSender** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateStreamMessage

Syntax

```
Function CreateStreamMessage() As StreamMessage
```

Description

Creates a **StreamMessage** object (see [“StreamMessage Object” on page 98](#)).

Parameters

None.

Return Value

A **StreamMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateTemporaryQueue

Syntax

```
Function CreateTemporaryQueue() As TemporaryQueue
```

Description

Creates a temporary queue.

Parameters

None.

Return Value

A temporary queue.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateTextMessage

Syntax

```
Function CreateTextMessage([Text]) As TextMessage
```

Description

Creates a **TextMessage** object (see [“TextMessage Object” on page 113](#)).

Parameters

Name	Type	Description
Text	Variant	The string used to initialize the message.

Return Value

A **TextMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Recover

Syntax

```
Sub Recover()
```

Description

Stops message delivery in this session, and then restarts message delivery with the oldest unacknowledged message.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Rollback

Syntax

```
Sub Rollback()
```

Description

Rolls back any messages processed in this transaction and releases any locks currently held.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Run

Syntax

```
Sub Run()
```

Description

An optional operation that is only intended to be used by Application Servers and not by ordinary JMS clients.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.22 session Object

The **session** object is a single threaded context for producing and consuming messages.

4.22.1 session Properties

The **session** object includes the properties listed in Table 20.

Table 20 Properties of the session Object

Property	Data Type	Description
MessageListener	MessageListener	This is not currently supported.
Transacted	Boolean	Returns an indicator of whether the session is in transacted mode. A value of true indicates the session is in transacted mode; a value of false indicates it is not. This property is read-only.

4.22.2 session Methods

The **session** object includes the following methods:

- **Commit** on page 95
- **CreateBytesMessage** on page 96
- **CreateMapMessage** on page 96
- **CreateMessage** on page 96
- **CreateStreamMessage** on page 96
- **CreateTextMessage** on page 97
- **Recover** on page 97
- **Rollback** on page 97
- **Run** on page 98

Commit

Syntax

```
Sub Commit()
```

Description

Commits all messages processed in this transaction and releases any locks currently held.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateBytesMessage

Syntax

```
Function CreateBytesMessage() As BytesMessage
```

Description

Creates a **BytesMessage** object (see [“BytesMessage Object” on page 45](#)).

Parameters

None.

Return Value

A **BytesMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateMapMessage

Syntax

```
Function CreateMapMessage() As MapMessage
```

Description

Creates a **MapMessage** object (see [“MapMessage Object” on page 60](#)).

Parameters

None.

Return Value

A **MapMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateMessage

Syntax

```
Function CreateMessage() As message
```

Description

Creates a **message** object (see [“message Object” on page 73](#)).

Parameters

None.

Return Value

A **message** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateStreamMessage

Syntax

```
Function CreateStreamMessage() As StreamMessage
```

Description

Creates a **StreamMessage** object (see [“StreamMessage Object” on page 98](#)).

Parameters

None.

Return Value

A **StreamMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateTextMessage

Syntax

```
Function CreateTextMessage([Text]) As TextMessage
```

Description

Creates a **TextMessage** object (see [“TextMessage Object” on page 113](#)).

Parameters

Name	Type	Description
Text	Variant	The string used to initialize the message.

Return Value

A **TextMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Recover

Syntax

```
Sub Recover()
```

Description

Stops message delivery for the session, and then restarts message delivery starting with the oldest unacknowledged message.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Rollback

Syntax

```
Sub Rollback()
```

Description

Rolls back any messages processed in this transaction and releases any locks currently held.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Run

Syntax

Sub Run ()

Description

An optional operation that is only intended to be used by Application Servers and not by ordinary JMS clients.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.23 **StreamMessage Object**

The **StreamMessage** object is used to send a stream of primitive data types.

4.23.1 **StreamMessage Properties**

The **StreamMessage** object includes the properties listed in Table 21.

Table 21 Properties of the StreamMessage Object

Property	Data Type	Description
CorrelationID	String	Sets or returns correlation ID values that are either JMS IQ Manager message IDs or application-specific strings.
CorrelationIDAsBytes	Variant	Sets or returns the correlation ID as an array of bytes for the message.
DeliveryMode	DeliveryModeConstants	Sets or returns the delivery mode for this message as either msNonPersistent, or msPersistent. The default value is msDefaultDeliveryMode (msPersistent). See DeliveryMode Constants on page 44.

Table 21 Properties of the StreamMessage Object

Property	Data Type	Description
Destination	Destination	Sets or returns the destination for the message.
Expiration	Currency	Sets or returns the message expiration time in milliseconds.
MessageID	String	Sets or returns the value of the uniquely assigned identifier in the message header.
Priority	PriorityConstants	Sets or returns the priority assigned to the message. Possible values are 1 - 9.
Redelivered	Boolean	Sets or returns an indicator of whether the message is redelivered. A value of true indicates the message is redelivered; a value of false indicates it is not.
ReplyTo	Destination	Sets or returns the destination to which a reply to the message is sent. A destination can be a Topic, Queue, Temporary Topic, or a Temporary Queue.
Timestamp	Currency	Sets or returns the timestamp of the message.
Type	String	Sets or returns the message type.

4.23.2 StreamMessage Methods

The **StreamMessage** object includes the following methods:

- **Acknowledge** on page 100
- **ClearBody** on page 100
- **ClearProperties** on page 100
- **GetProperty** on page 101
- **PropertyExists** on page 101
- **ReadBoolean** on page 102
- **ReadByte** on page 102
- **ReadBytes** on page 102
- **ReadChar** on page 103
- **ReadDouble Method** on page 103
- **ReadFloat** on page 103
- **ReadInt** on page 104
- **ReadString** on page 105
- **Reset** on page 105
- **SetProperty** on page 106
- **WriteBoolean** on page 106
- **WriteByte** on page 106
- **WriteBytes** on page 107
- **WriteChar** on page 107
- **WriteDouble** on page 108
- **WriteFloat** on page 108
- **WriteInt** on page 108
- **WriteLong** on page 109
- **WriteObject** on page 109

- [ReadLong Method](#) on page 104
- [ReadObject](#) on page 104
- [ReadShort](#) on page 105
- [WriteShort](#) on page 109
- [WriteString](#) on page 110

Acknowledge

Syntax

```
Sub Acknowledge()
```

Description

Acknowledges the receipt of current and previous messages.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ClearBody

Syntax

```
Sub ClearBody()
```

Description

Clears the body of a message, leaving the message header values and property entries intact.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ClearProperties

Syntax

```
Sub ClearProperties()
```

Description

Clears the properties from a message, leaving the message header fields and body intact.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

GetProperty

Syntax

```
Function GetProperty(name As String)
```

Description

Returns the Visual Basic data type property value with the given name into the message.

Parameters

Name	Type	Description
name	String	The name of the property.

Return Value

The value of the specified property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

PropertyExists

Syntax

```
Function PropertyExists(name As String) As Boolean
```

Description

Checks whether a value for a specific property exists.

Parameters

Name	Type	Description
name	String	The name of the property to check.

Return Value

A Boolean indicator of whether a value exists for the specified property. If the property value exists, the return value is **true**; otherwise, it is **false**.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadBoolean

Syntax

```
Function ReadBoolean() As Boolean
```

Description

Reads a Boolean value from the message stream.

Parameters

None.

Return Value

The value of the Boolean property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadByte

Syntax

```
Function ReadByte() As Byte
```

Description

Reads a signed 8-bit value from the message stream.

Parameters

None.

Return Value

The value of the Byte property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadBytes

Syntax

```
Function ReadBytes(value, [length As Long]) As Long
```

Description

Reads a portion of the message stream.

Parameters

Name	Type	Description
value	Variant	The buffer into which the data is read.
length	Long	The number of bytes to read. This number must be less than or equal to value length.

Return Value

The value of the bytes read into the buffer.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadChar

Syntax

```
Function ReadChar() As Short
```

Description

Reads a Unicode character value from the message stream.

Parameter

None.

Return Value

The value of the character property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadDouble Method

Syntax

```
Function ReadDouble() As Double
```

Description

Reads a double value from the message stream.

Parameters

None.

Return Value

The value of the double property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadFloat

Syntax

```
Function ReadFloat() As Single
```

Description

Reads a floating point value from the message stream.

Parameters

None.

Return Value

The value of the floating point property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadInt

Syntax

```
Function ReadInt() As Long
```

Description

Reads a signed 32-bit integer value from the message stream.

Parameters

None.

Return Value

The value of the integer property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadLong Method

Syntax

```
Function ReadLong() As Currency
```

Description

Reads a signed 64-bit integer value from the message stream.

Parameters

None.

Return Value

The value of the long property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadObject

This method is not currently supported.

ReadShort

Syntax

```
Function ReadShort() As Integer
```

Description

Reads a signed 16-bit number from the message stream.

Parameters

None.

Return Value

The value of the short property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReadString

Syntax

```
Function ReadString() As String
```

Description

Reads in a string from the stream message.

Parameters

None.

Return Value

The value of the String property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Reset

Syntax

```
Sub Reset()
```

Description

Places the message body in read-only mode and repositions the stream to the beginning.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

SetProperty

Syntax

```
Sub SetProperty(name As String, value)
```

Description

Sets a Visual Basic data type value into the message property with the specified name.

Parameters

Name	Type	Description
name	String	The name of the property.
value	Variant	The value to set in the specified property.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteBoolean

Syntax

```
Sub WriteBoolean(value As Boolean)
```

Description

Writes a Boolean value to the message stream as a 1-byte value.

Parameters

Name	Type	Description
value	Boolean	The value to write.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteByte

Syntax

```
Sub WriteByte(value As Byte)
```

Description

Writes a 1-byte value to the message stream.

Parameters

Name	Type	Description
value	Byte	The value to write.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteBytes

Syntax

```
Sub WriteBytes(value, [offset], [length])
```

Description

Writes a byte array, or a portion of the byte array, to the message stream.

Parameters

Name	Type	Description
value	Variant	The byte array value to write.
offset	Variant	The initial offset within the byte array.
length	Variant	The number of bytes to use.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteChar

Syntax

```
Sub WriteChar(value As Short)
```

Description

Writes a char value to the message stream as a 2-byte value, high byte first.

Parameters

Name	Type	Description
value	Short	The value to write.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteDouble

Syntax

```
Sub WriteDouble(value As Double)
```

Description

Converts the double parameter value to a long value, and then writes an 8-byte long value to the message stream (high byte is written first).

Parameters

Name	Type	Description
value	Double	The value to write.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteFloat

Syntax

```
Sub WriteFloat(value As Single)
```

Description

Converts the floating point argument to a long value, and then writes a 4-byte long value to the message stream (high byte is written first).

Parameters

Name	Type	Description
value	Single	The value to write.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteInt

Syntax

```
Sub WriteInt(value As Long)
```

Description

Writes a number to the message stream as a 4-byte integer (high byte is written first).

Parameters

Name	Type	Description
value	Long	The value to write.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteLong

Syntax

```
Sub WriteLong(value As Currency)
```

Description

Writes a number to the message stream as an 8-byte long value (high byte is written first).

Parameters

Name	Type	Description
value	Currency	The value to write.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteObject

This method is not currently supported.

WriteShort

Syntax

```
Sub WriteShort(value As Integer)
```

Description

Writes a number to the message stream as a 2-byte short integer (high byte is written first).

Parameters

Name	Type	Description
value	Integer	The value to write.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

WriteString

Syntax

```
Sub WriteString(value As String)
```

Description

Writes a string to the message stream.

Parameters

Name	Type	Description
value	String	The value to write.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.24 TemporaryQueue Object

A **TemporaryQueue** is a unique **Queue** object created for the duration of a **QueueConnection**.

4.24.1 TemporaryQueue Properties

The **TemporaryQueue** object includes the property listed in Table 22.

Table 22 Properties of the TemporaryQueue Object

Property	Data Type	Description
QueueName	String	Returns the name of the queue. This property is read-only.

4.24.2 TemporaryQueue Object Methods

The TemporaryQueue object includes the following methods:

- **Delete** on page 111
- **ToString** on page 111

Delete

Syntax

```
Sub Delete()
```

Description

Deletes the temporary queue.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ToString

Syntax

```
Function ToString() As String
```

Description

Returns a printed version of the queue name.

Parameters

None.

Return Value

A String representation of the queue name.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.25 TemporaryTopic Object

A **TemporaryTopic** is a unique Topic object created for the duration of a TopicConnection.

4.25.1 TemporaryTopic Properties

The **TemporaryTopic** object includes the property listed in Table 23.

Table 23 Properties of the TemporaryTopic Object

Property	Data Type	Description
TopicName	String	Returns the name of the topic. This property is read-only.

4.25.2 TemporaryTopic Methods

The **TemporaryTopic** object includes the following methods:

- **Delete** on page 112
- **ToString** on page 112

Delete

Syntax

```
Sub Delete()
```

Description

Deletes the temporary topic.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ToString

Syntax

```
Function ToString() As String
```

Description

Returns a printed version of the topic name.

Parameters

None.

Return Value

A String representation of the topic name.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.26 TextMessage Object

A `TextMessage` is used to send a message containing a `String`.

4.26.1 TextMessage Properties

The `TextMessage` object includes the properties listed in Table 24.

Table 24 Properties of the TextMessage Object

Property	Data Type	Description
CorrelationID	String	Sets or returns correlation ID values that are either JMS IQ Manager message IDs or application-specific strings.
CorrelationIDAsBytes	Variant	Sets or returns the correlation ID as an array of bytes for the message.
DeliveryMode	DeliveryModeConstants	Sets or returns the delivery mode for this message as either <code>msNonPersistent</code> , or <code>msPersistent</code> . The default value is <code>msDefaultDeliveryMode</code> (<code>msPersistent</code>). See DeliveryMode Constants on page 44.
Destination	Destination	Sets or returns the destination for this message.
Expiration	Currency	Sets or returns the message expiration time in milliseconds.
MessageID	String	Sets or returns the value of the uniquely assigned identifier in the message header.
Priority	PriorityConstants	Sets or returns the priority assigned to the message. Possible values are 1 - 9.
Redelivered	Boolean	Sets or returns an indicator of whether the message is redelivered. A value of true indicates the message is redelivered; a value of false indicates it is not.
ReplyTo	Destination	Sets or returns the destination to which a reply to the message is sent. A destination can be a <code>Topic</code> , <code>Queue</code> , <code>Temporary Topic</code> , or a <code>Temporary Queue</code> .
Text	String	Sets or returns the text of the message.
Timestamp	Currency	Sets or returns the timestamp of the message.
Type	String	Sets or returns the message type.

4.26.2 TextMessage Methods

The **TextMessage** object includes the following methods:

- **Acknowledge** on page 114
- **ClearBody** on page 114
- **ClearProperties** on page 114
- **GetProperty** on page 115
- **PropertyExists** on page 115
- **SetProperty** on page 116

Acknowledge

Syntax

```
Sub Acknowledge()
```

Description

Acknowledges the receipt of current and previous messages.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ClearBody

Syntax

```
Sub ClearBody()
```

Description

Clears the body of a message, leaving the message header values and property entries intact.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ClearProperties

Syntax

```
Sub ClearProperties()
```

Description

Clears the properties from a message, leaving the message header fields and body intact.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

GetProperty

Syntax

```
Function GetProperty(name As String)
```

Description

Returns the Visual Basic data type property value with the given name into the message.

Parameters

Name	Type	Description
name	String	The name of the property.

Return Value

The value of the specified property.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

PropertyExists

Syntax

```
Function PropertyExists(name As String) As Boolean
```

Description

Checks whether a value for a specific property exists.

Parameters

Name	Type	Description
name	String	The name of the property to check.

Return Value

A Boolean indicator of whether a value exists for the specified property. If the property value exists, the return value is **true**; otherwise, it is **false**.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

SetProperty

Syntax

```
Sub SetProperty(name As String, value)
```

Description

Sets a Visual Basic data type value into the message property with the specified name.

Parameters

Name	Type	Description
name	String	The name of the property.
value	Variant	The value to set in the specified property.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.27 Topic Object

A **Topic** object encapsulates a message service-specific topic name.

4.27.1 Topic Properties

The **Topic** object includes the property listed in Table 25.

Table 25 Properties of the Topic Object

Property	Data Type	Description
TopicName	String	Returns the name of the topic. This property is read-only.

4.27.2 Topic Methods

The **Topic** object includes the following method:

- **ToString** on page 117

ToString

Syntax

```
Function ToString() As String
```

Description

Returns a printed version of the topic name.

Parameters

None.

Return Value

A String representation of the topic name.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.28 TopicConnection Object

A **TopicConnection** is an active connection to a pub/sub message service.

4.28.1 TopicConnection Properties

The **TopicConnection** object includes the properties listed in Table 26.

Table 26 Properties of the TopicConnection Object

Property	Data Type	Description
ClientID	String	Sets or returns a client identifier for the connection.
MetaData	ConnectionMetaData	This is not currently supported.

4.28.2 TopicConnection Methods

The **TopicConnection** object includes the following methods:

- [CreateTopicSession](#) on page 117
- [Start](#) on page 118
- [Stop](#) on page 118

CreateTopicSession

Syntax

```
Function CreateTopicSession(Transacted As Boolean, acknowledgeMode As AcknowledgeModeConstants) As TopicSession
```

Description

Creates a **TopicSession** using the specified transacted and acknowledge modes.

Parameters

Name	Type	Description
Transacted	Boolean	An indicator of the whether the session is transacted. A value of true indicates the session is transacted; false means it is not.
acknowledgeMode	AcknowledgeModeConstants	An indicator of the acknowledgement mode. See AcknowledgeMode Constants on page 43 for possible values.

Return Value

A topic session.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Start

Syntax

```
Sub Start()
```

Description

Starts or restarts a connection's delivery of incoming messages.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Stop

Syntax

```
Function Stop()
```

Description

Temporarily stops a connection's delivery of incoming messages.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.29 TopicConnectionFactory Object

A client uses a **TopicConnectionFactory** to create a **TopicConnection** for a pub/sub message service.

4.29.1 TopicConnectionFactory Properties

The **TopicConnectionFactory** object includes the properties listed in Table 27.

Table 27 Properties of the TopicConnectionFactory Object

Property	Data Type	Description
HostName	String	Sets or returns the name of the host where the message service is running.
Port	Long	Sets or returns the port number at which the message service is listening. The default value is 24053 .
PortOffset	Long	Sets or returns the port offset number of the message service if more than one service is running on the same host machine and using the same port number.

4.29.2 TopicConnectionFactory Methods

The **TopicConnectionFactory** object includes the following method:

- [CreateTopicConnection](#) on page 119
- [CreateTopicConnectionEx](#) on page 120

CreateTopicConnection

Syntax

```
Function CreateTopicConnection() As TopicConnection
```

Description

Creates a topic connection with a default user identity.

Parameters

None.

Return Value

A topic connection.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateTopicConnectionEx

Syntax

```
Function CreateTopicConnection(userId As String, password As String)  
As TopicConnection
```

Description

Creates a topic connection with the specified user identity.

Parameters

Name	Type	Description
userId	String	The logon user ID.
password	String	The password associated with the specified user ID.

Return Value

A topic connection.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.30 TopicPublisher Object

A client uses a **TopicPublisher** for publishing messages on a topic.

4.30.1 TopicPublisher Properties

The **TopicPublisher** object includes the properties listed in Table 28.

Table 28 Properties of the TopicPublisher Object

Property	Data Type	Description
DeliveryMode	DeliveryModeConstants	Sets or returns the delivery mode for this message as either msNonPersistent, or msPersistent. The default value is msDefaultDeliveryMode (msPersistent). See DeliveryMode Constants on page 44.

Table 28 Properties of the TopicPublisher Object

Property	Data Type	Description
DisableMessageID	Boolean	Sets or returns an indicator of whether message IDs are disabled. A value of true indicates message IDs are disabled; false indicates they are not.
DisableMessageTimestamp	Boolean	Sets or returns an indicator of whether timestamping is disabled. A value of true indicates timestamping is disabled; false indicates it is not.
Priority	PriorityConstants	This is not currently supported.
TimeToLive	Currency	Sets or returns the default length of time in milliseconds from its dispatch time that a produced message should be retained by the message system. The default value is msDefaultTimeToLive (0 (zero), which is unlimited).
Topic	Topic	Returns the topic associated with the topic publisher.

4.30.2 TopicPublisher Methods

The **TopicPublisher** object includes the following method:

- **Publish** on page 121

Publish

Syntax

```
Sub Publish(message As message, [DeliveryMode], [Priority], [TimeToLive], [Topic])
```

Description

Publishes a message to a topic for an unidentified message producer, specifying delivery mode, priority, time to live, and receiving topic.

Parameters

Name	Type	Description
message	message	The message to publish.
DeliveryMode	Variant	The delivery mode for the message. See DeliveryMode Constants on page 44.
Priority	Variant	The priority for the message (not currently supported).
TimeToLive	Variant	The lifetime of the message in milliseconds.

Name	Type	Description
Topic	Variant	The topic to which the message should be published.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.31 TopicRequestor Object

The **TopicRequestor** object provides a helper class to simplify making service requests.

4.31.1 TopicRequestor Methods

The **TopicRequestor** object includes the following methods:

- [Close](#) on page 122
- [Create](#) on page 122
- [Request](#) on page 123

Close

Syntax

```
Sub Close()
```

Description

Closes the topic requestor.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Create

Syntax

```
Sub Create(session As TopicSession, Topic As Topic)
```

Description

Creates a topic requestor.

Parameters

Name	Type	Description
session	TopicSession	The topic session.
Topic	Topic	The topic associated with the topic requestor.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Request

Syntax

```
Function Request(message As message, [timeOut]) As message
```

Description

Sends a request to the topic and waits for a reply, optionally for a specified amount of time.

Parameters

Name	Type	Description
message	message	The message to send.
timeOut	Variant	The timeout value for the message in milliseconds.

Return Value

A reply message.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.32 TopicSession Object

A **TopicSession** provides methods for creating TopicPublishers, TopicSubscribers, and TemporaryTopics.

4.32.1 TopicSession Properties

The **TopicSession** object includes the properties listed in Table 29.

Table 29 Properties of the TopicSession Object

Property	Data Type	Description
MessageListener	MessageListener	This is not currently supported.
Transacted	Boolean	Returns an indicator of whether the session is in transacted mode. A value of true indicates the session is in transacted mode; a value of false indicates it is not. This property is read-only.

4.32.2 TopicSession Methods

The **TopicSession** object includes the following methods:

- [Commit](#) on page 124
- [CreateBytesMessage](#) on page 125
- [CreateDurableSubscriber](#) on page 125
- [CreateMapMessage](#) on page 126
- [CreateMessage](#) on page 126
- [CreatePublisher](#) on page 126
- [CreateStreamMessage](#) on page 127
- [CreateSubscriber](#) on page 127
- [CreateTemporaryTopic](#) on page 128
- [CreateTextMessage](#) on page 128
- [CreateTopic](#) on page 128
- [Recover](#) on page 129
- [Rollback](#) on page 129
- [Run](#) on page 130
- [Unsubscribe](#) on page 130

Commit

Syntax

```
Sub Commit()
```

Description

Commits all messages processed in this transaction and releases any resources currently held.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateBytesMessage

Syntax

```
Function CreateBytesMessage() As ByteMessage
```

Description

Creates a **ByteMessage** object (see [“ByteMessage Object” on page 45](#)).

Parameters

None.

Return Value

A **ByteMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateDurableSubscriber

Syntax

```
Function CreateDurableSubscriber(Topic As Topic, name As String,  
[MessageSelector], [NoLocal]) As TopicSubscriber
```

Description

Creates a durable subscriber for the specified topic.

Parameters

Name	Type	Description
Topic	Topic	The non-temporary topic to which to subscribe.
name	String	The name used to identify this subscription.
MessageSelector	Variant	The message selector expression that a message's properties must match in order to be delivered. Null can be used.
NoLocal	Variant	An indicator of whether messages published by the topic subscriber's own connection can be delivered. Set this value to true to prevent the delivery of messages published by the topics own connection; set it to false to allow delivery.

Return Value

A **TopicSubscriber** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateMapMessage

Syntax

```
Function CreateMapMessage() As MapMessage
```

Description

Creates a **MapMessage** object (see [“MapMessage Object” on page 60](#)).

Parameters

None.

Return Value

A **MapMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateMessage

Syntax

```
Function CreateMessage() As message
```

Description

Creates a **message** object (see [“message Object” on page 73](#)).

Parameters

None.

Return Value

A **message** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreatePublisher

Syntax

```
Function CreatePublisher(Topic As Topic) As TopicPublisher
```

Description

Creates a **TopicPublisher** to publish messages to the specified topic.

Parameters

Name	Type	Description
Topic	Topic	The topic to which to publish, or null, if this is an unidentified producer.

Return Value

A **TopicPublisher** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateStreamMessage

Syntax

```
Function CreateStreamMessage() As StreamMessage
```

Description

Creates a **StreamMessage** object (see [“StreamMessage Object” on page 98](#)).

Parameters

None.

Return Value

A **StreamMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateSubscriber

Syntax

```
Function CreateSubscriber(Topic As Topic, [MessageSelector],  
[NoLocal]) As TopicSubscriber
```

Description

Creates a non-durable subscriber to the specified topic.

Parameters

Name	Type	Description
Topic	Topic	The topic to which to subscribe.
MessageSelector	Variant	The message selector expression that a message's properties must match in order to be delivered. Null can be used.
NoLocal	Variant	An indicator of whether messages published by the topic subscriber's own connection can be delivered. Set this value to true to prevent the delivery of messages published by the topics own connection; set it to false to allow delivery.

Return Value

A **TopicSubscriber** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateTemporaryTopic

Syntax

```
Function CreateTemporaryTopic() As TemporaryTopic
```

Description

Creates a temporary topic.

Parameters

None.

Return Value

A temporary topic.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateTextMessage

Syntax

```
Function CreateTextMessage([Text]) As TextMessage
```

Description

Creates a **TextMessage** object (see [“TextMessage Object” on page 113](#)).

Parameters

Name	Type	Description
Text	Variant	The string used to initialize the message.

Return Value

A **TextMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateTopic

Syntax

```
Function CreateTopic(TopicName As String) As Topic
```

Description

Creates a topic identity given a topic name.

Parameters

Name	Type	Description
TopicName	String	The name of the topic to create.

Return Value

A **Topic** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Recover

Syntax

```
Sub Recover()
```

Description

Stops message delivery in this session, and then restarts message delivery with the oldest unacknowledged message.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Rollback

Syntax

```
Sub Rollback()
```

Description

Rolls back any messages processed in this transaction and releases any locks currently held.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Run

Syntax

```
Sub Run()
```

Description

An optional operation that is only intended to be used by Application Servers and not by ordinary JMS clients.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Unsubscribe

Syntax

```
Sub Unsubscribe(name As String)
```

Description

Unsubscribes a durable subscription that was created by a client.

Parameters

Name	Type	Description
name	String	The name used to identify this subscription.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.33 TopicSubscriber Object

A client uses a **TopicSubscriber** for receiving messages that have been published to a topic.

4.33.1 TopicSubscriber Properties

The **TopicSubscriber** object includes the properties listed in Table 30.

Table 30 Properties of the TopicSubscriber Object

Property	Data Type	Description
MessageListener	MessageListener	This is not currently supported.
MessageSelector	String	Returns the message selector expression for the message consumer. This property is read-only.
NoLocal	Boolean	Returns an indicator of whether messages published by the topic subscriber's own connection can be delivered. A value of true inhibits the delivery of messages published by its own connection; false allows delivery of such messages. This property is read-only.
Topic	Topic	Returns the topic associated with the topic subscriber.

4.33.2 TopicSubscriber Methods

The **TopicSubscriber** object includes the following methods:

- **Close** on page 131
- **Receive** on page 132
- **ReceiveNoWait** on page 132

Close

Syntax

```
Sub Close()
```

Description

Closes the topic subscriber. A message service might allocate resources on behalf of a message consumer, so the receiver should be closed when it is no longer needed.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Receive

Syntax

```
Function Receive([timeOut]) As message
```

Description

Receives the next message produced or the next message that arrives within the specified timeout interval for this message consumer

Parameters

Name	Type	Description
timeOut	Variant	The timeout value for the message consumer in milliseconds.

Return Value

A **message** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

ReceiveNoWait

Syntax

```
Function ReceiveNoWait() As message
```

Description

Receives the next message if one is immediately available.

Parameters

None

Return Value

A **message** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.34 XAQueueConnection Object

An **XAQueueConnection** object provides the same create options as **QueueConnection**. The only difference is that an **XAQueueConnection** is transacted by definition.

4.34.1 XAQueueConnection Properties

The **XAQueueConnection** object includes the properties listed in Table 31.

Table 31 Properties of the XAQueueConnection Object

Property	Data Type	Description
ClientID	String	Sets or returns the client identifier for the connection.
Metadata	ConnectionMetaData	This is not currently supported.

4.34.2 XAQueueConnection Methods

The **XAQueueConnection** object includes the following methods:

- [CreateQueueSession](#) on page 133
- [CreateXAQueueSession](#) on page 134
- [Start](#) on page 134
- [Stop](#) on page 134

CreateQueueSession

Syntax

```
Function CreateQueueSession(Transacted As Boolean, acknowledgeMode As AcknowledgeModeConstants) As QueueSession
```

Description

Creates a **QueueSession** using the specified transacted and acknowledge modes.

Parameters

Name	Type	Description
Transacted	Boolean	An indicator of the whether the session is transacted. A value of true indicates the session is transacted; false means it is not.
acknowledgeMode	AcknowledgeModeConstants	An indicator of the acknowledgement mode. See AcknowledgeMode Constants on page 43 for possible values.

Return Value

A queue session.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateXAQueueSession

Syntax

```
Function CreateXAQueueSession() As XAQueueSession
```

Description

Creates an **XAQueueSession** object.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Start

Syntax

```
Sub Start()
```

Description

Starts or restarts a connection's delivery of incoming messages.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Stop

Syntax

```
Sub Stop()
```

Description

Temporarily stops a connection's delivery of incoming messages.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.35 XAQueueConnectionFactory Object

An **XAQueueConnectionFactory** object provides the same create options as **QueueConnectionFactory**. The only difference is that an **XAQueueConnectionFactory** object is transacted by definition.

4.35.1 XAQueueConnectionFactory Object Properties

The **XAQueueConnectionFactory** object includes the properties listed in Table 32.

Table 32 Properties of the XAQueueConnectionFactory Object

Property	Data Type	Description
HostName	String	Sets or returns the name of the host where the message service is running.
Port	Long	Sets or returns the port number at which the message service is listening. The default value is 24053 .
PortOffset	Long	Sets or returns the port offset number of the message service if more than one service is running on the same host machine and using the same port number.

4.35.2 XAQueueConnectionFactory Methods

The **XAQueueConnectionFactory** object includes the following methods:

- [CreateQueueConnection](#) on page 135
- [CreateQueueConnectionEx](#) on page 136
- [CreateXAQueueConnection](#) on page 136
- [CreateXAQueueConnectionEx](#) on page 136

CreateQueueConnection

Syntax

```
Function CreateQueueConnection() As QueueConnection
```

Description

Creates a queue connection with a default user identity.

Parameters

None.

Return Value

A queue connection.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateQueueConnectionEx

Syntax

```
Function CreateQueueConnection(userId As String, password As String)  
As QueueConnection
```

Description

Creates a queue connection with the specified user identity.

Parameters

Name	Type	Description
userId	String	The logon user ID.
password	String	The password associated with the specified user ID.

Return Value

A queue connection.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateXAQueueConnection

Syntax

```
Function CreateXAQueueConnection() As XAQueueConnection
```

Description

Creates an XA queue connection with a default user identity.

Parameters

None.

Return Value

An XA queue connection.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateXAQueueConnectionEx

Syntax

```
Function CreateQueueConnection(userId As String, password As String)  
As XAQueueConnection
```

Description

Creates an XA queue connection with the specified user identity.

Parameters

Name	Type	Description
userId	String	The logon user ID.
password	String	The password associated with the specified user ID.

Return Value

An XA queue connection.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.36 XAQueueSession Object

An **XAQueueSession** object provides a regular **QueueSession**, with the exception that it is transacted by definition. It can be used to create the following objects: **QueueReceiver**, **QueueSender**, and **QueueBrowser**.

4.36.1 XAQueueSession Properties

The **XAQueueSession** object includes the properties listed in Table 33.

Table 33 Properties of the XAQueueSession Object

Property	Data Type	Description
MessageListener	MessageListener	This is not currently supported.
QueueSession	QueueSession	Returns the queue session associated with the XAQueueSession . This property is read-only.
Transacted	Boolean	Returns an indicator of whether the session is in transacted mode. A value of true indicates the session is in transacted mode; a value of false indicates it is not. This property is read-only.

4.36.2 XAQueueSession Methods

The **XAQueueSession** object includes the following methods:

- **Commit** on page 138
- **CreateTextMessage** on page 139

- [CreateBytesMessage](#) on page 138
- [CreateMapMessage](#) on page 138
- [CreateMessage](#) on page 139
- [CreateStreamMessage](#) on page 139
- [Recover](#) on page 140
- [Rollback](#) on page 140
- [Run](#) on page 141

Commit

Syntax

```
Sub Commit()
```

Description

Commit all messages processed in this transaction and releases any locks currently held.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateBytesMessage

Syntax

```
Function CreateBytesMessage() As BytesMessage
```

Description

Creates a **BytesMessage** object (see [“BytesMessage Object” on page 45](#)).

Parameters

None.

Return Value

A **BytesMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateMapMessage

Syntax

```
Function CreateMapMessage() As MapMessage
```

Description

Creates a **MapMessage** object (see [“MapMessage Object” on page 60](#)).

Parameters

None.

Return Value

A **MapMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateMessage

Syntax

```
Function CreateMessage() As message
```

Description

Creates a **message** object (see [“message Object” on page 73](#)).

Parameters

None.

Return Value

A **message** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateStreamMessage

Syntax

```
Function CreateStreamMessage() As StreamMessage
```

Description

Creates a **StreamMessage** object (see [“StreamMessage Object” on page 98](#)).

Parameters

None.

Return Value

A **StreamMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateTextMessage

Syntax

```
Function CreateTextMessage([Text]) As TextMessage
```

Description

Creates a **TextMessage** object (see [“TextMessage Object” on page 113](#)).

Parameters

Name	Type	Description
Text	Variant	The string used to initialize the message.

Return Value

A **TextMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Recover

Syntax

```
Sub Recover()
```

Description

Stops message delivery in this session, and then restarts message delivery with the oldest unacknowledged message.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Rollback

Syntax

```
Sub Rollback()
```

Description

Rolls back any messages processed in this transaction and releases any locks currently held.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Run

Syntax

```
Sub Run()
```

Description

An optional operation that is only intended to be used by Application Servers and not by ordinary JMS clients.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.37 XASession Object

The **XASession** object extends the capability of **session** by adding access to a message service's support for transacted messages using the Compensating Resource Manager (CRM), handled under the Distributed Transaction Coordinator (DTC).

4.37.1 XASession Object Properties

The **XASession** object includes the properties listed in Table 34.

Table 34 Properties of the XASession Object

Property	Data Type	Description
MessageListener	MessageListener	This is not currently supported.
Transacted	Boolean	Returns an indicator of whether the session is in transacted mode. A value of true indicates the session is in transacted mode; a value of false indicates it is not. This property is read-only.

4.37.2 XASession Object Methods

The **XASession** object includes the following methods:

- **Commit** on page 142
- **CreateBytesMessage** on page 142
- **CreateMapMessage** on page 142
- **CreateMessage** on page 143
- **CreateTextMessage** on page 143
- **Recover** on page 144
- **Rollback** on page 144
- **Run** on page 145

- [CreateStreamMessage](#) on page 143

Commit

Syntax

```
Sub Commit()
```

Description

Commits all messages processed in this transaction and releases any locks currently held.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateBytesMessage

Syntax

```
Function CreateBytesMessage() As BytesMessage
```

Description

Creates a **BytesMessage** object (see [“BytesMessage Object” on page 45](#)).

Parameters

None.

Return Value

A **BytesMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateMapMessage

Syntax

```
Function CreateMapMessage() As MapMessage
```

Description

Creates a **MapMessage** object (see [“MapMessage Object” on page 60](#)).

Parameters

None.

Return Value

A **MapMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateMessage

Syntax

```
Function CreateMessage() As message
```

Description

Creates a **message** object (see [“message Object” on page 73](#)).

Parameters

None.

Return Value

A **message** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateStreamMessage

Syntax

```
Function CreateStreamMessage() As StreamMessage
```

Description

Creates a **StreamMessage** object (see [“StreamMessage Object” on page 98](#)).

Parameters

None.

Return Value

A **StreamMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateTextMessage

Syntax

```
Function CreateTextMessage([Text]) As TextMessage
```

Description

Creates a **TextMessage** object (see [“TextMessage Object” on page 113](#)).

Parameters

Name	Type	Description
Text	Variant	The string used to initialize the message.

Return Value

A **TextMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Recover

Syntax

```
Sub Recover()
```

Description

Stops message delivery for the session, and then restarts message delivery starting with the oldest unacknowledged message.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Rollback

Syntax

```
Sub Rollback()
```

Description

Rolls back any messages processed in this transaction and releases any locks currently held.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Run

Syntax

```
Sub Run()
```

Description

An optional operation that is only intended to be used by Application Servers and not by ordinary JMS clients.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.38 XATopicConnection Object

An **XATopicConnection** provides the same create options as **TopicConnection**, but is transacted by definition.

4.38.1 XATopicConnection Properties

The **XATopicConnection** object includes the properties listed in Table 35.

Table 35 Properties of the XATopicConnection Object

Property	Data Type	Description
ClientID	String	Sets or returns a client identifier for the connection.
MetaData	ConnectionMetaData	This is not currently supported.

4.38.2 XATopicConnection Methods

The **XATopicConnection** object includes the following methods:

- [CreateTopicSession](#) on page 146
- [Start](#) on page 147
- [Stop](#) on page 147

CreateTopicSession

Syntax

```
Function CreateTopicSession(Transacted As Boolean, acknowledgeMode As AcknowledgeModeConstants) As TopicSession
```

Description

Creates a **TopicSession** using the specified transacted and acknowledge modes.

Parameters

Name	Type	Description
Transacted	Boolean	An indicator of the whether the session is transacted. A value of true indicates the session is transacted; false means it is not.
acknowledgeMode	AcknowledgeModeConstants	An indicator of the acknowledgement mode. See AcknowledgeMode Constants on page 43 for possible values.

Return Value

A topic session.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateXATopicSession

Syntax

```
Function CreateXATopicSession() As XATopicSession
```

Description

Creates an **XATopicSession** using the specified transacted and acknowledge modes.

Parameters

Name	Type	Description
Transacted	Boolean	An indicator of the whether the session is transacted. A value of true indicates the session is transacted; false means it is not.
acknowledgeMode	AcknowledgeModeConstants	An indicator of the acknowledgement mode. See AcknowledgeMode Constants on page 43 for possible values.

Return Value

An XA topic session.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Start

Syntax

```
Sub Start()
```

Description

Starts or restarts a connection's delivery of incoming messages.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Stop

Syntax

```
Function Stop()
```

Description

Temporarily stops a connection's delivery of incoming messages.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.39 XATopicConnectionFactory Object

An **XATopicConnectionFactory** object provides the same create options as a **TopicConnectionFactory** object, but is transacted by definition.

4.39.1 XATopicConnectionFactory Properties

The **XATopicConnectionFactory** object includes the properties listed in Table 36.

Table 36 Properties of the XATopicConnectionFactory Object

Property	Data Type	Description
HostName	String	Sets or returns the name of the host where the message service is running.
Port	Long	Sets or returns the port number at which the message service is listening. The default value is 24053 .
PortOffset	Long	Sets or returns the port offset number of the message service if more than one service is running on the same host machine and using the same port number.

4.39.2 XATopicConnectionFactory Methods

The **XATopicConnectionFactory** object includes the following method:

- [CreateTopicConnection](#) on page 148
- [CreateTopicConnectionEx](#) on page 149
- [CreateXATopicConnection](#) on page 149
- [CreateXATopicConnectionEx](#) on page 149

CreateTopicConnection

Syntax

```
Function CreateTopicConnection() As TopicConnection
```

Description

Creates a topic connection with a default user identity.

Parameters

None.

Return Value

A topic connection.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateTopicConnectionEx

Syntax

```
Function CreateTopicConnection(userId As String, password As String)  
As TopicConnection
```

Description

Creates a topic connection with the specified user identity.

Parameters

Name	Type	Description
userId	String	The logon user ID.
password	String	The password associated with the specified user ID.

Return Value

A topic connection.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateXATopicConnection

Syntax

```
Function CreateXATopicConnection() As XATopicConnection
```

Description

Creates an XA topic connection with a default user identity.

Parameters

None.

Return Value

An XA topic connection.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateXATopicConnectionEx

Syntax

```
Function CreateXATopicConnection(userId As String, password As String)  
As XATopicConnection
```

Description

Creates an XA topic connection with the specified user identity.

Parameters

Name	Type	Description
userId	String	The logon user ID.
password	String	The password associated with the specified user ID.

Return Value

An XA topic connection.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.40 XATopicSession Object

An **XATopicSession** provides a regular **TopicSession** object, with the exception that it is transacted by definition. It can be used to create **TopicSubscriber** and **TopicPublisher** objects.

4.40.1 XATopicSession Properties

The **XATopicSession** object includes the properties listed in Table 37.

Table 37 Properties of the XATopicSession Object

Property	Data Type	Description
MessageListener	MessageListener	This is not currently supported.
TopicSession	TopicSession	Returns the topic session associated with the XATopicSession . This property is read-only.
Transacted	Boolean	Returns an indicator of whether the session is in transacted mode. A value of true indicates the session is in transacted mode; a value of false indicates it is not. This property is read-only.

4.40.2 XATopicSession Methods

The **XATopicSession** object includes the following methods:

- **Commit** on page 151
- **CreateBytesMessage** on page 151
- **CreateMapMessage** on page 151
- **CreateTextMessage** on page 152
- **Recover** on page 153
- **Rollback** on page 153

- [CreateMessage](#) on page 152
 - [Run](#) on page 154
 - [CreateStreamMessage](#) on page 152
-

Commit

Syntax

```
Sub Commit()
```

Description

Commits all messages processed in this transaction and releases any resources currently held.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateBytesMessage

Syntax

```
Function CreateBytesMessage() As BytesMessage
```

Description

Creates a **BytesMessage** object (see [“BytesMessage Object” on page 45](#)).

Parameters

None.

Return Value

A **BytesMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateMapMessage

Syntax

```
Function CreateMapMessage() As MapMessage
```

Description

Creates a **MapMessage** object (see [“MapMessage Object” on page 60](#)).

Parameters

None.

Return Value

A **MapMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateMessage

Syntax

```
Function CreateMessage() As message
```

Description

Creates a **message** object (see [“message Object” on page 73](#)).

Parameters

None.

Return Value

A **message** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateStreamMessage

Syntax

```
Function CreateStreamMessage() As StreamMessage
```

Description

Creates a **StreamMessage** object (see [“StreamMessage Object” on page 98](#)).

Parameters

None.

Return Value

A **StreamMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

CreateTextMessage

Syntax

```
Function CreateTextMessage([Text]) As TextMessage
```

Description

Creates a **TextMessage** object (see [“TextMessage Object” on page 113](#)).

Parameters

Name	Type	Description
Text	Variant	The string used to initialize the message.

Return Value

A **TextMessage** object.

This method also returns a long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Recover

Syntax

```
Sub Recover()
```

Description

Stops message delivery in this session, and then restarts message delivery with the oldest unacknowledged message.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Rollback

Syntax

```
Sub Rollback()
```

Description

Rolls back any messages processed in this transaction and releases any locks currently held.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

Run

Syntax

```
Sub Run()
```

Description

An optional operation that is only intended to be used by Application Servers and not by ordinary JMS clients.

Parameters

None.

Return Value

A long value representing the result status. A value of 0 (zero) indicates the function was successful; any other value indicates there was an error.

4.41 Error Codes

Common error codes in the COM+ API are given below.

4.41.1 IErrorInfo Methods

Table 38 IErrorInfo Methods

IErrorInfo Methods	Description
GetDescription	Returns a textual description of the error.
GetGUID	Returns the globally unique identifier (GUID) for the interface that defined the error.

4.41.2 HRESULT Errors

```
static HRESULT Error( LPCOLESTR lpszDesc, const IID& iid = GUID_NULL,
    HRESULT hRes = 0 );
```

Description

This static method sets up the IErrorInfo interface to provide error information to the client. In order to call Error, your object must implement the ISupportErrorInfo interface.

If the hRes parameter is nonzero, then Error returns the value of hRes. If hRes is zero, then the first four versions of Error return DISP_E_EXCEPTION. The last two versions return the result of the macro MAKE_HRESULT(1, FACILITY_ITF, nID).

Table 39 HRESULT Values

Value	Description
E_FAIL	Failure.
E_NOTIMPL	Method is not supported.
S_FALSE	Success. Condition was FALSE.
S_OK	Success. Numerically equivalent to NOERROR.

4.41.3 Error Value Constants

Table 40 lists the possible error values and provides an explanation of what each means.

Table 40 Error Value Constants

Error Value Constant	Description
Const msErrGeneral = 768 (&H300)	JMS exception, unspecified.
Const msErrReAlloc = 769 (&H301)	A JMS exception occurred as a result of memory reallocation.
Const msErrMalloc = 770 (&H302)	A JMS exception occurred as a result of memory allocation.
Const msErrConnection = 771 (&H303)	A JMS exception occurred in setting up a connection.
Const msErrCreation = 772 (&H304)	A JMS exception occurred while creating a JMS object.
Const msErrCloseSocket = 773 (&H305)	A JMS exception occurred because of a closed socket.
Const msErrMessageEOF = 774 (&H306)	Processing ended because the BytesMessage or StreamMessage ended unexpectedly.
Const msErrMessageNotReadable = 775 (&H307)	Processing ended because the message could not be read.
Const msErrMessageNotWriteable = 776 (&H308)	Processing ended because the message could not be written.
Const msErrMessageFormat = 777 (&H309)	Processing ended because the JMS client attempted to use a data type not supported by the message (or a message property), or attempted to read message data (or a message property) as the wrong type.
Const msErrTransactionRolledBack = 778 (&H30A)	The attempt to commit the session was unsuccessful of a transaction being rolled back.

Table 40 Error Value Constants

Error Value Constant	Description
Const msErrIllegalState = 779 (&H30B)	Processing ended because a method was invoked at an illegal or inappropriate time or because the provider was not in an appropriate state for the requested operation.
Const msErrInvalidDestination = 780 (&H30C)	Processing ended because the destination could not be understood or was found to be invalid.
Const msErrNotImplemented = 781 (&H30D)	Processing ended because a feature or interface was not implemented.
Const msErrIndexOutOfBounds = 782 (&H30E)	Processing ended because an index of some sort (such as to an array, to a string, or to a vector) was found to be outside the valid range.
Const msErrNullPointer = 783 (&H30F)	Processing ended because the pointer in a case where an object was required.
Const msErrInvalidClientID = 784 (&H310)	Processing ended because the connection's client ID was rejected by the provider.
Const msErrInvalidSelector = 785 (&H311)	Processing ended because the message selector was found to be syntactically invalid.
Const msErrSecurity = 786 (&H312)	Processing was ended by JMS Security – for example, the provider rejected a name/ password combination submitted by a client.
Const msErrResourceAllocation = 787 (&H313)	Processing ended because of the provider was unable to allocate resources required for the method/function.
Const msErrTransactionInProgress = 788 (&H314)	Processing ended because a transaction was in progress.

Working with the COM+ API Samples

The eGate API Kit for JMS IQ Manager includes code and Project samples. This chapter describes how to use the code samples to build a sample COM+ application for JMS IQ Manager, and then describes how to run the sample application through the JMS Server.

What's in This Chapter

- [About the COM+ Samples](#) on page 157
- [Implementing the Java CAPS Projects](#) on page 158
- [Building the Sample COM+ Application](#) on page 159
- [Building the CRM Sample Application](#) on page 161
- [Running the Sample COM+ Applications](#) on page 165

5.1 About the COM+ Samples

The eGate API Kit provides COM+ code samples and Enterprise Designer Project samples designed to work together to demonstrate different types of JMS messaging using a COM+ client and eGate Integrator. The sample Projects provide examples of the following messaging types:

- Publish/subscribe (queues or topics)
- Request-reply (queues or topics)
- Message selector (topics)
- Publish/subscribe using XA (topics)

The sample file, **eGateAPIKit_Sample.zip**, contains the **.zip** files listed in Table 41. The table describes what each **.zip** file contains.

Table 41 eGate API Kit Samples

File Name	Contents
CodeSamples.zip	The sample code files for use on Windows.
CodeSamplesUNIX.tar	The sample code files for use on UNIX operating systems.

Table 41 eGate API Kit Samples

File Name	Contents
Sample_Project.zip	The sample Java CAPS Projects that you can import into Enterprise Designer. The Project to use with the COM+ sample code is in Sample_Project.zip .

5.2 Implementing the Java CAPS Projects

The sample Java CAPS Projects include one Project and several sub-Projects, each used to demonstrate a different type of JMS messaging. Each Project uses one of three available pass-through Collaborations to deliver messages between senders and receivers or between publishers and subscribers.

Before continuing, make sure you have downloaded the sample file as described in [“Installing the eGate API Kit” on page 16](#). Implementing the sample Projects consists of the following steps.

- [Importing the Sample Project](#) on page 158
- [Creating the Environment](#) on page 159
- [Deploying the Projects](#) on page 159

5.2.1 Importing the Sample Project

To work with the sample Projects for Enterprise Designer, you first need to import the Projects into Enterprise Designer.

To import the sample Project into Enterprise Designer

- 1 If you have not already done so, extract **eGateAPIKit_Sample.zip**.
- 2 Start Enterprise Designer.
- 3 From the Repository context menu, select **Import Project**.
- 4 A message box appears, prompting you to save any unsaved changes to the Repository.
 - A If you want to save your changes and have not already done so, click **No**. Save your changes, and then re-select **Import Project**.
 - B If you have saved all changes, click **Yes**.
- 5 Click the **Browse** button to display the Open File dialog.
- 6 Locate and select **Sample_Project.zip**, located in the directory in which you extracted **ProjectSamples.zip**.
- 7 Click **Open** to select the file.

The Import Manager dialog appears.

- 8 Click **Import** to import the file.

Note: *An error message might appear, stating that certain APIs are missing. This error is not serious. Click **Continue** to proceed with the import.*

The Import Status message box appears after the file is imported successfully.

- 9 Click **OK** to close the message box.
- 10 When you are finished importing files, click **Close** to close the Import Manager dialog. The Project Explorer is automatically refreshed from the Repository.

5.2.2 Creating the Environment

In order to deploy the Projects to a Logical Host, you must create an Environment used by all sub-Projects. Use the Environment Explorer of Enterprise Designer to create a new Environment and Logical Host. The Logical Host must include a Sun SeeBeyond JMS IQ Manager and Integration Server (IS). For more information about Environments, see the *Sun SeeBeyond eGate Integrator User's Guide* or the *Sun SeeBeyond eGate Integrator System Administration Guide*.

5.2.3 Deploying the Projects

For each sample sub-Project, you must create a Deployment Profile, and then build and deploy the Project. You can use the Automap feature of the Deployment Profile to map each Project component to its corresponding Environment component.

Before deploying the sub-Projects, make sure the Logical Host for the sample applications is started. For more information about Deployment Profiles, see the *Sun SeeBeyond eGate Integrator User's Guide* or the *Sun SeeBeyond eGate Integrator System Administration Guide*.

5.3 Building the Sample COM+ Application

The sample COM+ files are provided in both Microsoft Visual Studio 6.0 format and Microsoft .NET 2003 format. Before building the sample applications, you need to configure the environment. Follow these steps to build the sample applications:

- [Setting up the Directory Structure](#) on page 160
- [Configuring the Sample Environment](#) on page 160
- [Building the Sample Applications](#) on page 160

Table 42 lists each messaging type demonstrated in the samples along with their corresponding folder names and the name of the queue or topic you need to specify for each sample.

Table 42 COM+ Sample Information

Messaging Type Sample Directory Name	Executable	Sending Topic or Queue	Receiving Topic or Queue
Queue Send and Receive \Point2Point_Sample	p2p.exe	P2PSample	eGateP2PSample
Queue Requestor \QueueRequestor_Sample	queurequestor.exe	QueueRequestor Sample	OutputQueue
Topic Publish and Subscribe \PublishSubscribe_Sample	pubsub.exe	PubSubSample	eGatePubSubSample
Topic Requestor \TopicRequestor_Sample	topicrequest.exe	TopicRequestor Sample	OutputTopic
Topic Selector \MessageSelector_Sample	messageselector.exe	Selector	eGateSelector
XA Publish and Subscribe \XA_Sample	xatest	XAPubSubSample	eGateXAPubSubSample
CRM \CRM_Sample	CRMClient.exe	XAPubSubSample	eGateXAPubSubSample

5.3.1 Setting up the Directory Structure

The sample files must be located in a specific directory in relation to the API kit library files.

To set up the directory structure

- 1 Navigate to the location where you extracted **eGateAPIKIT_Sample.zip**.
- 2 From the extracted files, extract **CodeSamples.zip**.
- 3 In the extracted folders, navigate to the \apikit folder and copy the \com folder to the location where you installed the eGate API Kit at the same level as the \jms folder. The \com folder contains all of the sample files.

5.3.2 Configuring the Sample Environment

In order to compile the COM+ sample client applications (or any client applications you create), you must edit the PATH variable by adding the path to the library files you downloaded during installation (see **“Post-Installation Instructions” on page 17**). Make sure this has been completed before performing the following steps.

5.3.3 Building the Sample Applications

All samples provided with the toolkit have make files, and the project files can be edited and compiled in both Visual Studio 6.0 and .NET 2003 except XA_Sample and CRM_Sample, which require Visual Studio 6.0.

The CRM sample requires additional setup. To build the CRM application, follow the steps outlined in [“Building the CRM Sample Application” on page 161](#).

To build the sample COM+ applications

Important: Make sure to build the CRM sample before building the XA sample. The XA sample requires the newly-built **CRMTTest.dll** file to compile.

- 1 To access the sample project you want to compile, do one of the following:
 - ♦ To open the project in Visual Studio, open the **.vbp** file for the sample (see [Table 42 on page 160](#) for sample file locations).
 - ♦ To open the project in .NET, open the **.sln** file for the sample. This file is located in the <project_name>.NET folder in the sample directory (see [Table 42 on page 160](#) for sample file locations).
- 2 Before building a sample, change the hostname and port number values where ever they occur in the project.
- 3 Save your changes to the project, and then build the project.

5.4 Building the CRM Sample Application

There are three primary steps to setting up the CRM sample application. Perform the steps in the following order:

- [Creating a Database for the CRM Sample](#) on page 161
- [Configuring and Building the CRM Sample](#) on page 163
- [Creating the CRM Sample Application](#) on page 164


5.4.1 Creating a Database for the CRM Sample

In order to use the Compensating Resource Manager (CRM) samples provided, you must create a SQL Server database named “CRM”.

Creating a SQL Server Database

- 1 Create a SQL Server database, using the name “CRM” for the purpose of testing the samples.
- 2 Create a table, using the name “Messages”.
- 3 Create two columns in the table, “UID” and “Message”.
- 4 From the Control Panel, select **Administrative Tools** and then double-click **Data Sources (ODBC)**.
- 5 On the ODBC Data Source Administrator window, click **Add**, and then select **SQL_Server**. Click **Finish** to continue.


Figure 22 SQL Database Source



- 6 Provide the name of the data source, a description if desired, and the machine name on which SQL Server is running. Click **Next** to continue.


Important: You will not be able to continue until a successful connection is made.

Figure 23 SQL Data source




- 7 Select **With Windows authentication using the network logon ID**, select **Connect to SQL Server** to obtain default settings for the additional configuration options, and then click **Next**.

Figure 24 Login Settings



- 8 For the default database, select the database you created earlier from the drop-down list. Click **Next** to continue.

Figure 25 Default SQL Server Database



- 9 Click **Finish**.

5.4.2 Configuring and Building the CRM Sample

Two sample files are used to run the CRM sample. The samples can be found in the location where you extracted the sample files under `\CodeSamples\apikit\com`. The files used are:

- `\CRM_Sample\CRMDLL\CRMTest.vbp`
- `\CRM_Sample\CRMDLL\CRMTest.dll`

To configure the CRM

- 1 Using Visual Studio 6.0, open **CRMTest.vbp**.
- 2 Follow the comments in the code of the following files to modify the sample to your system requirements. Make sure to customize all instances of hostname and port.
 - ♦ InsertMessage.cls
 - ♦ TwoTasks.cls
 - ♦ TopicTask.cls
 - ♦ QueueTasks.cls
- 3 Save your changes and recompile the sample application.
- 4 Copy **CRMclient.exe** (located in the CRM_Sample folder) to the machine on which the external code is to run.
- 5 On the machine where you copied **CRMclient.exe**, register the file **CRMTest.dll** into the Windows registry by running the following command:

```
regsvr32 your_path_location\CRMTest.dll
```


5.4.3 Creating the CRM Sample Application

Once the CRM sample has been recompiled, use the Windows Component Services administrative tools to create the COM+ Application.

To create the CRM sample application

- 1 From the Control Panel, select **Administrative Tools** and then **Component Services**.
- 2 Expand the Component Services folder, and then right click on **COM+ Applications**.
Select **New** and then select **Application**. The COM+ Application Install Wizard appears.
- 3 On the Welcome page, click **Next**, and then select **Create an empty application**.
- 4 Enter **CRM_TEST** as the name of the new application (you can use any name), and then select **Library application** as the Activation Type.

Figure 26 CRM_TEST Application



- 5 Click **Next**, and then click **Finish**.
- 6 On the Component services window, expand the **CRM_TEST** component.
- 7 Right-click the **Components** folder, click **New**, and then click **Component**. The COM+ Component Install Wizard appears.
- 8 On the Welcome window, click **Next**, and then click **Install new component(s)**.
- 9 Browse to the location of the recently compiled **CRMTest.dll** and click **Open**.
- 10 Accept the remainder of the default settings, and then click **Next** and **Finish**.

5.5 Running the Sample COM+ Applications

There are several different sample applications you can run. Each sends and receives a simple message, using a Collaboration in the Java CAPS sample Project to transfer the message. You can use Enterprise Manager to monitor the activity of the Projects.


For information about the project names and locations referenced below, see [Table 42 on page 160](#).

To run a send/receive or publish/subscribe sample application

- 1 Navigate to the directory containing the sample you want to run.
- 2 Double-click the executable file. If you compiled using .NET, the executable is located in the sample directory in \<project_name>.NET\bin. If you compiled using Visual Studio, the executable is in the sample directory.

A dialog appears.

Figure 27 Point 2 Point Sample Dialog



- 3 On the dialog, enter the name of the producer topic or queue, change the message if desired, and then click **Publish** or **Send**.
- 4 Change the queue or topic name to the consumer topic or queue, and then click **Receive**.

A message appears stating whether the message was processed.

To run the selector sample application

- 1 Navigate to the directory containing the sample you want to run.
- 2 Double-click the executable file. If you compiled using .NET, the executable is located in the sample directory in \`<project_name>.NET\bin`. If you compiled using Visual Studio, the executable is in the sample directory.

A dialog appears.

- 3 On the dialog, enter the name of the producer topic, change the message if desired, select the **Match** option, and then click **Publish**.
- 4 Change the topic name to the consumer topic, and then click **Receive**.

The text of the message appears in the **Received Message** field.

To run a requestor sample application

- 1 Navigate to the directory containing the sample you want to run.
- 2 Double-click the executable file. If you compiled using .NET, the executable is located in the sample directory in \`<project_name>.NET\bin`. If you compiled using Visual Studio, the executable is in the sample directory.

A dialog appears.

- 3 On the dialog, enter the name of the requester topic or queue, change the message if desired, and then click **Start**.

The text of the message appears in the **Received Message** field.

To run an XA sample application

Note: The **CRMTTest.dll** file must be registered on the machine on which the XA sample resides before you can run the XA sample.

- 1 Navigate to the directory containing the sample you want to run.
- 2 Double-click the executable file (the executable is in the sample directory).
A dialog appears.
- 3 On the dialog, do the following:
 - A Enter the name of the producer topic or queue.
 - B Change the message if desired.
 - C Select **Topic** to publish via a Topic; deselect **Topic** to send via a Queue.
 - D Select **Commit** to send the message.
 - E Click **Publish**.
- 4 Repeat steps 2 and 3 with the following changes:
 - ♦ Enter the name of the *consumer* topic or queue.
 - ♦ Click **Receive** instead of **Publish**.

To run the CRM sample application

Note: Make sure you have completed all of the steps in **“Building the CRM Sample Application” on page 161**.

- 1 Navigate to the directory containing the sample you want to run.
- 2 Double-click the executable file (the executable is in the sample directory).
A dialog appears.
- 3 On the dialog, do the following:
 - A Enter the name of the producer topic or queue.
 - B Change the message if desired.
 - C Select **Commit** to send the message.
 - D Click **Publish**.
- 4 Repeat steps 2 and 3 with the following changes:
 - ♦ Enter the name of the *consumer* topic or queue.
 - ♦ Click **Receive** instead of **Publish**.

Index

Symbols

.NET 2003 159, 160

A

Acknowledge method 47, 62, 74, 100, 114
 acknowledge modes
 AutoAcknowledge 43
 ClientAcknowledge 44
 DupsOKAcknowledge 44
 AcknowledgeMode constants 43
 Administrative Tools 161
 AutoAcknowledge mode 43

B

body 21
 bytes message 22
 BytesMessage 22
 BytesMessage methods 46
 Acknowledge 47
 ClearBody 47
 ClearProperties 48
 GetProperty 48, 67
 PropertyExists 48
 ReadBoolean 49
 ReadByte 49
 ReadBytes 50
 ReadChar 50
 ReadDouble 50
 ReadFloat 51
 ReadInt 51
 ReadLong 51
 ReadShort 52
 ReadUnsignedByte 52
 ReadUnsignedShort 52
 ReadUTF 53
 Reset 53
 SetProperty 54
 WriteBoolean 54
 WriteByte 54, 106
 WriteBytes 55
 WriteChar 55
 WriteDouble 56

 WriteFloat 56
 WriteInt 56
 WriteLong 57
 WriteObject 57
 WriteShort 57
 WriteUTF 58
 BytesMessage object 45, 73
 BytesMessage properties 46
 CorrelationID 46
 CorrelationIDAsBytes 46
 DeliveryMode 46
 Destination 46
 Expiration 46
 MessageID 46
 Priority 46
 Redelivered 46
 ReplyTo 46
 Timestamp 46
 Type 46

C

ClearBody method 47, 62, 75, 100, 114
 ClearMessage methods
 ClearProperties 62
 ClearProperties method 48, 62, 75, 100, 114
 ClientAcknowledge mode 44
 ClientID property 80, 117, 133, 145
 Close method 77, 84, 86, 122, 131
 CodeSamples.zip 157
 CodeSamplesUNIX.tar 157
 Collaborations 158
 COM+ applications 29, 31
 COM+ library 27
 Commit method 89, 95, 124, 138, 142, 151
 compensating resource manager 27
 about 27
 architecture 27
 configuring 29
 implementing 28
 two-phase commit protocol 28
 Component Services 29
 Connection methods
 Start 59
 Stop 59
 Connection object 58
 Connection properties 58
 ConnectionFactory object 59
 ConnectionFactory properties 59
 HostName 59
 Port 60
 PortOffset 60
 ConnectionMetaData object 60
 constants

- AcknowledgeMode constants 43
 - DeliveryMode constants 44
 - message 44
 - miscellaneous 44
 - msDefaultDeliveryMode 45
 - msDefaultPriority 45
 - msDefaultTimeToLive 45
 - Priority 45
 - conventions, text 13
 - correlation ID 22, 24
 - CorrelationID property 46, 60, 73, 98, 113
 - CorrelationIDAsBytes property 46, 60, 73, 98, 113
 - Create method 86, 122
 - CreateBytesMessage method 90, 95, 125, 138, 142, 151
 - CreateDurableSubscriber method 125
 - CreateMapMessage method 90, 96, 126, 138, 142, 151
 - CreateMessage method 90, 96, 126, 139, 143, 152
 - CreatePublisher method 126
 - CreateQueue method 91
 - CreateQueueConnection method 83, 135
 - CreateQueueConnectionEx method 83, 136
 - CreateQueueSession method 81, 133
 - CreateReceiver method 91
 - CreateSender method 92
 - CreateStreamMessage method 92, 96, 127, 139, 143, 152
 - CreateSubscriber method 127
 - CreateTemporaryQueue method 92
 - CreateTemporaryTopic method 128
 - CreateTextMessage method 93, 97, 128, 140, 143, 152
 - CreateTopic method 128
 - CreateTopicConnection method 119, 148
 - CreateTopicConnectionEx method 120, 149
 - CreateTopicSession method 117, 146
 - CreateXAQueueConnection method 136
 - CreateXAQueueConnectionEx method 137
 - CreateXAQueueSession method 134
 - CreateXATopicConnection method 149
 - CreateXATopicConnectionEx method 149
 - CreateXATopicSession method 146
 - CRM 27
 - about 27
 - architecture 27
 - configuring 29
 - implementing 28
 - two-phase commit protocol 28
 - CRM sample 161
 - building 161
 - configuring 163
 - creating the application 164
 - database 161
 - running 167
 - CRMClient.exe 164
 - CRMTTest.dll 161, 164
- ## D
- data format 20
 - defaults
 - Message interface 44
 - Delete method 111, 112
 - delivery mode 21
 - delivery modes
 - msNonPersistent 44
 - msPersistent 44
 - DeliveryMode constants 44
 - DeliveryMode property 46, 60, 73, 79, 87, 98, 113, 120
 - Deployment Profile 159
 - destination 21, 41
 - Destination property 46, 60, 73, 99, 113
 - destinations 26, 43
 - DisableMessageID property 79, 87, 121
 - DisableMessageTimestamp property 79, 87, 121
 - distributed transaction 27
 - Domain Manager 20
 - DupsOKAcknowledge mode 44
- ## E
- eGateAPIKitDocs.sar, installing 16
 - Enterprise Designer 157
 - Environment 159
 - error codes 154
 - expiration 21
 - Expiration property 46, 60, 73, 99, 113
- ## G
- GetBoolean method 63
 - GetByte method 63
 - GetBytes method 63
 - GetChar property 64
 - GetDouble method 64
 - GetFloat method 65
 - GetInt method 65
 - GetLong method 66
 - GetObject method 66
 - GetProperty method 48, 66, 75, 101
 - GetProperty methods 115
 - GetShort method 67
 - GetString method 67

H

header fields 21
 HostName property 59, 82, 119, 135, 148

I

Implementing 158
 implementing message server models 20
 IQ Manager field 21
 IQ Manager SSL field 21
 ItemExists method 67

J

Java 20
 Java CAPS Projects 158
 JMS API in C++
 differences with Java API 41
 JMS interfaces 18
 JMSCorrelationID 22, 24
 JMSDeliveryMode 21
 JMSDestination 21
 JMSExpiration 21
 JMSMessageID 21
 JMSPriority 22
 JMSRedelivered 22
 JMSReplyTo 22
 JMSTimestamp 21

L

Logical Host 19, 159

M

MapMessage 22
 MapMessage methods 61
 Acknowledge 62
 ClearBody 62
 GetBoolean 63
 GetByte 63
 GetBytes 63
 GetChar 64
 GetDouble 64
 GetFloat 65
 GetInt 65
 GetLong 66
 GetObject 66
 GetProperty 66
 GetShort 67
 ItemExists 67
 PropertyExists 68
 SetBoolean 68

 SetByte 69
 SetBytes 69
 SetChar 70
 SetDouble 70
 SetFloat 70
 SetInt 71
 SetLong 71
 SetObject 72
 SetProperty 72
 SetShort 72
 SetString 73
 MapMessage object 60, 73
 MapMessage properties 60
 CorrelationID 60
 CorrelationIDAsBytes 60
 DeliveryMode 60
 Destination 60
 Expiration 60
 MapNames 61
 MessageID 61
 Priority 61
 Redelivered 61
 ReplyTo 61
 Timestamp 61
 Type 61
 MapNames property 61
 Message 22
 Message constants 45
 message constants 44
 message consumer 41
 message ID 21
 Message interface defaults 44
 message methods 74
 Acknowledge 74
 ClearBody 75
 ClearProperties 75
 GetProperty 75
 PropertyExists 76
 SetProperty 76
 message object 73
 message producer 41
 message properties 73
 CorrelationID 73
 CorrelationIDAsBytes 73
 DeliveryMode 73
 Destination 73
 Expiration 73
 MessageID 74
 Priority 74
 Redelivered 74
 ReplyTo 74
 Timestamp 74
 Type 74
 message selector 26

- message server models 20
 - MessageConsumer method
 - ReceiveNoWait 78
 - MessageConsumer methods 77
 - Close 77
 - ReceiveMessage 77
 - MessageConsumer object 77
 - MessageConsumer properties 77
 - MessageListener 77
 - MessageSelector 77
 - MessageID property 46, 61, 74, 99, 113
 - MessageListener object 78
 - MessageListener property 77, 84, 89, 94, 124, 131, 137, 141, 150
 - MessageProducer object 78
 - MessageProducer properties 79
 - DeliveryMode 79
 - DisableMessageID 79
 - DisableMessageTimestamp 79
 - Priority 79
 - TimeToLive 79
 - messages 41
 - body (payload) 21, 22
 - header fields 21
 - JMSCorrelationID 22
 - JMSDeliveryMode 21
 - JMSDestination 21
 - JMSExpiration 21
 - JMSMessageID 21
 - JMSPriority 22
 - JMSRedelivered 22
 - JMSReplyTo 22
 - JMSTimestamp 21
 - properties 21, 22
 - MessageSelector property 77, 84, 131
 - MetaData property 80, 117, 133, 145
 - methods
 - BytesMessage 46
 - MapMessage 61
 - message 74
 - MessageConsumer 77
 - Queue 80
 - QueueConnection 81
 - QueueConnectionFactory 82
 - QueueReceiver 84
 - QueueRequestor 85
 - QueueSender 88
 - QueueSession 89
 - session 95
 - StreamMessage 99
 - TemporaryTopic 112
 - TextMessage 114
 - Topic 116
 - TopicConnection 117
 - TopicConnectionFactory 119
 - TopicPublisher 121
 - TopicRequestor 122
 - TopicSession 124
 - TopicSubscriber 131
 - XAQueueConnection 133
 - XAQueueConnectionFactory 135
 - XAQueueSession 137
 - XASession 141
 - XATopicConnection 145
 - XATopicConnectionFactory 148
 - XATopicSession 150
 - miscellaneous constants 44
 - msDefaultDeliveryMode constant 45
 - msDefaultPriority constant 45
 - msDefaultTimeToLive constant 45
 - msNonPersistent mode 44
 - msPersistent mode 44
 - multi-threaded apartment model 26
- ## N
- NoLocal property 131
- ## O
- ODBC Data Source Administrator 161
- ## P
- payload 21
 - point-to-point messaging 24
 - port number 20
 - Port property 60, 82, 119, 135, 148
 - PortOffset property 60, 82, 119, 135, 148
 - priority 22
 - Priority constants 45
 - Priority property 46, 61, 74, 79, 87, 99, 113, 121
 - project samples
 - about 157
 - building 159, 160
 - CRM 161
 - building 161
 - configuring 163
 - creating the application 164
 - database 161
 - running 167
 - directory structure 160
 - environment 160
 - implementing 158
 - running 165–167
 - XA 161
 - properties 21, 22

- BytesMessage 46
- Connection 58
- ConnectionFactory 59
- MapMessage 60
- message 73
- MessageConsumer 77
- MessageProducer 79
- Queue 79
- QueueConnection 80
- QueueConnectionFactory 82
- QueueReceiver 84
- QueueSender 87
- QueueSession 89
- session 94
- StreamMessage 98
- TemporaryQueue 110
- TemporaryTopic 112
- TextMessage 113
- Topic 116
- TopicConnection 117
- TopicConnectionFactory 119
- TopicPublisher 120
- TopicSession 124
- TopicSubscriber 131
- XAQueueConnection 133
- XAQueueConnectionFactory 135
- XAQueueSession 137
- XASession 141
- XATopicConnectionFactory 148
- XATopicSession 145, 150
- PropertyExists method 48, 68, 76, 101, 115
- Publish method 121
- publish/subscribe messaging 23

Q

- Queue methods 80
 - ToString 80
- Queue object 79
- Queue properties 79
 - QueueName 79
- Queue property 84, 87
- QueueBrowser object 80
- QueueConnection methods 81
 - CreateQueueSession 81
 - Start 81
 - Stop 82
- QueueConnection object 80
- QueueConnection properties 80
 - ClientID 80
 - MetaData 80
- QueueConnectionFactory methods 82
 - CreateQueueConnection 83
 - CreateQueueConnectionEx 83

- QueueConnectionFactory object 82
- QueueConnectionFactory properties 82
 - HostName 82
 - Port 82
 - PortOffset 82
- QueueName property 79, 110
- QueueReceiver methods 84
 - Close 84
 - Receive 84
 - ReceiveNoWait 85, 132
- QueueReceiver object 83
- QueueReceiver properties 84
 - MessageListener 84
 - MessageSelector 84
 - Queue 84
- QueueRequestor methods 85
 - Close 86
 - Create 86
 - Request 86
- QueueRequestor object 85
- QueueSender methods 88
 - Send 88
- QueueSender object 87
- QueueSender properties 87
 - DeliveryMode 87
 - DisableMessageID 87
 - DisableMessageTimestamp 87
 - Priority 87
 - Queue 87
 - TimeToLive 88
- QueueSession methods 89
 - Commit 89
 - CreateBytesMessage 90
 - CreateMapMessage 90
 - CreateMessage 90
 - CreateQueue 91
 - CreateReceiver 91
 - CreateSender 92
 - CreateStreamMessage 92
 - CreateTemporaryQueue 92
 - CreateTextMessage 93
 - Recover 93
 - Rollback 94
 - Run 94
- QueueSession object 89
- QueueSession properties 89
 - MessageListener 89
 - Transacted 89
- QueueSession property 137

R

- ReadBoolean method 49, 102
- ReadByte method 49, 102

ReadBytes method 50, 102
 ReadChar method 50, 103
 ReadDouble method 50, 103
 ReadFloat method 51, 103
 ReadInt method 51, 104
 ReadLong method 51, 104
 ReadObject method 104
 ReadShort method 52, 105
 ReadString method 105
 ReadUnsignedByte method 52
 ReadUnsignedShort method 52
 ReadUTF method 53
 Receive Message method 77
 Receive method 84, 132
 ReceiveNoWait method 78, 85, 132
 Recover method 93, 97, 129, 140, 144, 153
 Redelivered property 46, 61, 74, 99, 113
 ReplyTo property 46, 61, 74, 99, 113
 Repository 19
 Request method 86, 123
 request/reply messaging 24
 requestor 41
 Reset method 53, 105
 Rollback method 94, 97, 129, 140, 144, 153
 Run method 94, 98, 130, 141, 145, 154

S

sample code for using JMS

- compensating resource manager (CRM) 161
- message selector
 - (discussed) 26
- publish/subscribe
 - (diagrammed) 23
- queue send/receive
 - (diagrammed) 24
- request-reply 24
 - (diagrammed) 25
- XA 26

 sample Projects

- importing 158

 Sample_Project.zip 158
 samples 157

- about 157
- building 159, 160
- CRM 161
 - building 161
 - configuring 163
 - creating the application 164
 - database 161
 - running 167
- directory structure 160
- environment 160
- implementing 158

running 165–167
 XA 161
 screenshots 13
 selector 26
 Send method 88
 send/receive messaging 24
 session 41
 Session methods

- CreateMapMessage 126

 session methods 95

- Commit 95
- CreateBytesMessage 95
- CreateMapMessage 96
- CreateMessage 96
- CreateStreamMessage 96
- CreateTextMessage 97
- Recover 97
- Rollback 97
- Run 98

 session object 94
 session properties 94

- MessageListener 94
- Transacted 94

 SetBoolean method 68
 SetByte method 69
 SetBytes method 69
 SetChar method 70
 SetDouble method 70
 SetFloat methods 70
 SetInt method 71
 SetLong method 71
 SetObject method 72
 SetProperty method 54, 72, 76, 106, 116
 SetShort method 72
 SetString method 73
 Start method 59, 81, 118, 134, 147
 STC_MSCOM.Compensator 35
 stc_mscom.dll 27, 31, 33, 39
 STC_MSCOM.XAQueueConnectionFactory 36
 STC_MSCOM.XATopicConnectionFactory 37
 SteamMessage methods

- Reset 105

 Stop method 59, 82, 118, 134, 147
 StreamMessage 22
 StreamMessage methods 99

- Acknowledge 100
- ClearBody 100
- ClearProperties 100
- GetProperty 101
- PropertyExists 101
- ReadBoolean 102
- ReadByte 102
- ReadBytes 102
- ReadChar 103

- ReadDouble 103
- ReadFloat 103
- ReadInt 104
- ReadLong 104
- ReadObject 104
- ReadShort 105
- ReadString 105
- setProperty 106
- WriteBoolean 106
- WriteBytes 107
- WriteChar 107
- WriteDouble 108
- WriteFloat 108
- WriteInt 108
- WriteLong 109
- WriteObject 109
- WriteShort 109
- WriteString 110
- StreamMessage object 73, 98
- StreamMessage properties 98
 - CorrelationID 98
 - CorrelationIDAsBytes 98
 - DeliveryMode 98
 - Destination 99
 - Expiration 99
 - MessageID 99
 - Priority 99
 - Redelivered 99
 - ReplyTo 99
 - Timestamp 99
 - Type 99
- supporting documents 13

T

- TemporaryQueue methods 111
- TemporaryQueue object 110
- TemporaryQueue properties 110
 - QueueName 110
- TemporaryTopic methods 112
 - Delete 111, 112
 - ToString 111, 112
- TemporaryTopic object 111
- TemporaryTopic properties 112
 - TopicName 112
- text conventions 13
- text message 23
- Text property 113
- TextMessage 23
- TextMessage methods 114
 - Acknowledge 114
 - ClearBody 114
 - ClearProperties 114
 - GetProperty 115
 - PropertyExists 115
 - setProperty 116
- TextMessage object 73, 113
- TextMessage properties 113
 - CorrelationID 113
 - CorrelationIDAsBytes 113
 - DeliveryMode 113
 - Destination 113
 - Expiration 113
 - MessageID 113
 - Priority 113
 - Redelivered 113
 - ReplyTo 113
 - Text 113
 - Timestamp 113
 - Type 113
- timestamp 21
- Timestamp property 46, 61, 74, 99, 113
- TimeToLive property 79, 88, 121
- Topic methods 116
 - ToString 117
- Topic object 116
- Topic properties 116
 - TopicName 116
- Topic property 121, 131
- TopicConnection methods 117
 - CreateTopicSession 117
 - Start 118
 - Stop 118
- TopicConnection object 117
- TopicConnection properties 117
 - ClientID 117
 - MetaData 117
- TopicConnectionFactory methods 119
 - CreateTopic 128
 - CreateTopicConnection 119
 - CreateTopicConnectionEx 120
- TopicConnectionFactory object 119
- TopicConnectionFactory properties 119
 - HostName 119
 - Port 119
 - PortOffset 119
- TopicName property 112, 116
- TopicPublisher methods 121
 - Publish 121
- TopicPublisher object 120
- TopicPublisher properties 120
 - DeliveryMode 120
 - DisableMessageID 121
 - DisableMessageTimestamp 121
 - Priority 121
 - TimeToLive 121
 - Topic 121
- TopicRequestor methods 122

- Close 122
- Create 122
- Request 123
- TopicRequestor object 122
- TopicSession method
 - CreateTemporaryTopic 128
- TopicSession methods 124
 - Commit 124
 - CreateBytesMessage 125
 - CreateDurableSubscriber 125
 - CreateMessage 126
 - CreatePublisher 126
 - CreateStreamMessage 127
 - CreateSubscriber 127
 - CreateTextMessage 128, 152
 - Recover 129
 - Rollback 129
 - Run 130
 - Unsubscribe 130
- TopicSession object 120, 123
- TopicSession properties 124
 - MessageListener 124
 - Transacted 124
- TopicSession property 150
- TopicSubscriber methods 131
 - Close 131
 - Receive 132
 - ReceiveNoWait 132
- TopicSubscriber object 130
- TopicSubscriber properties 131
 - MessageListener 131
 - MessageSelector 131
 - NoLocal 131
 - Topic 131
- Tostring method 80, 111, 112, 117
- Transacted property 89, 94, 124, 137, 141, 150
- Type property 46, 61, 74, 99, 113

U

- Unsubscribe method 130

V

- Visual Studio 159, 160

W

- WriteBoolean method 54, 106
- WriteByte method 54, 106
- WriteBytes method 55, 107
- WriteChar method 55, 107
- WriteDouble method 56, 108

- WriteFloat method 56, 108
- WriteInt method 56, 108
- WriteLong method 57, 109
- WriteObject method 57, 109
- WriteShort method 57, 109
- WriteString method 110
- WriteUTF method 58

X

- XA compliance 26
- XA sample 161
- XAConnection object 27
- XAConnectionFactory object 27
- XAQueueConnection methods 133
 - CreateQueueSession 133
 - CreateXAQueueSession 134
 - Start 134
 - Stop 134
- XAQueueConnection object 27, 132
- XAQueueConnection properties 133
 - ClientID 133
 - MetaData 133
- XAQueueConnectionFactory method
 - CreateQueueConnection 135
- XAQueueConnectionFactory methods 135
 - CreateQueueConnectionEx 136
 - CreateXAQueueConnection 136
 - CreateXAQueueConnectionEx 137
- XAQueueConnectionFactory object 27, 135
- XAQueueConnectionFactory properties 135
 - HostName 135
 - Port 135
 - PortOffset 135
- XAQueueSession methods 137
 - Commit 138
 - CreateBytesMessage 138
 - CreateMapMessage 138
 - CreateMessage 139
 - CreateStreamMessage 139
 - CreateTextMessage 140
 - Recover 140
 - Rollback 140
 - Run 141
- XAQueueSession object 27, 137
- XAQueueSession properties 137
 - MessageListener 137
 - QueueSession 137
 - Transacted 137
- XARecord object 28
- XASession methods 141
 - Commit 142
 - CreateBytesMessage 142
 - CreateMapMessage 142

- CreateMessage 143
- CreateStreamMessage 143
- CreateTextMessage 143
- Recover 144
- Rollback 144
- XASession object 28, 141
- XASession Object methods
 - Run 145
- XASession properties 141
 - MessageListener 141
 - Transacted 141
- XATopicConnection methods 145
 - CreateTopicSession 146
 - CreateXATopicSession 146
 - Start 147
 - Stop 147
- XATopicConnection object 28, 145
- XATopicConnection properties 145
 - ClientID 145
 - MetaData 145
- XATopicConnectionFactory methods 148
 - CreateTopicConnection 148
 - CreateTopicConnectionEx 149
 - CreateXATopicConnection 149
 - CreateXATopicConnectionEx 149
- XATopicConnectionFactory object 28, 147
- XATopicConnectionFactory properties 148
 - HostName 148
 - Port 148
 - PortOffset 148
- XATopicSession methods 150
 - Commit 151
 - CreateBytesMessage 151
 - CreateMapMessage 151
 - CreateMessage 152
 - CreateStreamMessage 152
 - Recover 153
 - Rollback 153
 - Run 154
- XATopicSession object 28, 150
- XATopicSession properties 150
 - MessageListener 150
 - TopicSession 150
 - Transacted 150