



# SunForum 3.2 Software User's Guide

---

Sun Microsystems, Inc.  
901 San Antonio Road  
Palo Alto, CA 94303-4900 U.S.A.  
650-960-1300

Part No. 816-1114-10  
April 2001, Revision A

[Send comments about this document to: docfeedback@sun.com](mailto:docfeedback@sun.com)

Copyright 2001 Sun Microsystems, Inc., 901 San Antonio Road • Palo Alto, CA 94303 USA. All rights reserved.

This product or document is protected by copyright and distributed under licenses restricting its use, copying, distribution, and decompilation. No part of this product or document may be reproduced in any form by any means without prior written authorization of Sun and its licensors, if any. Third-party software, including font technology, is copyrighted and licensed from Sun suppliers.

Parts of the product may be derived from Berkeley BSD systems, licensed from the University of California. UNIX is a registered trademark in the U.S. and other countries, exclusively licensed through X/Open Company, Ltd.

Sun, Sun Microsystems, the Sun logo, Sun Ray, Ultra, ShowMe, Sun Workstation, AnswerBook2, SunForum, and Solaris are trademarks, registered trademarks, or service marks of Sun Microsystems, Inc. in the U.S. and other countries. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. in the U.S. and other countries. Products bearing SPARC trademarks are based upon an architecture developed by Sun Microsystems, Inc. PostScript is a trademark of Adobe Systems Incorporated, which may be registered in certain jurisdictions. For SunForum 3.2, the following notice applies: Copyright DATA CONNECTION LIMITED 2001 Copyright TELES AG 2001 DATA CONNECTION® is a registered trademark of DATA CONNECTION LIMITED in the U.S. and other countries.

The OPEN LOOK and Sun™ Graphical User Interface was developed by Sun Microsystems, Inc. for its users and licensees. Sun acknowledges the pioneering efforts of Xerox in researching and developing the concept of visual or graphical user interfaces for the computer industry. Sun holds a non-exclusive license from Xerox to the Xerox Graphical User Interface, which license also covers Sun's licensees who implement OPEN LOOK GUIs and otherwise comply with Sun's written license agreements.

Federal Acquisitions: Commercial Software—Government Users Subject to Standard License Terms and Conditions.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESSED OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

---

Copyright 2001 Sun Microsystems, Inc., 901 San Antonio Road • Palo Alto, CA 94303 Etats-Unis. Tous droits réservés.

Ce produit ou document est protégé par un copyright et distribué avec des licences qui en restreignent l'utilisation, la copie, la distribution, et la décompilation. Aucune partie de ce produit ou document ne peut être reproduite sous aucune forme, par quelque moyen que ce soit, sans l'autorisation préalable et écrite de Sun et de ses bailleurs de licence, s'il y en a. Le logiciel détenu par des tiers, et qui comprend la technologie relative aux polices de caractères, est protégé par un copyright et licencié par des fournisseurs de Sun.

Des parties de ce produit pourront être dérivées des systèmes Berkeley BSD licenciés par l'Université de Californie. UNIX est une marque déposée aux Etats-Unis et dans d'autres pays et licenciée exclusivement par X/Open Company, Ltd.

Sun, Sun Microsystems, le logo Sun, Sun Ray, Ultra, ShowMe, Sun Workstation, AnswerBook2, SunForum, et Solaris sont des marques de fabrique ou des marques déposées, ou marques de service, de Sun Microsystems, Inc. aux Etats-Unis et dans d'autres pays. Toutes les marques SPARC sont utilisées sous licence et sont des marques de fabrique ou des marques déposées de SPARC International, Inc. aux Etats-Unis et dans d'autres pays. Les produits portant les marques SPARC sont basés sur une architecture développée par Sun Microsystems, Inc. PostScript est une marque de fabrique d'Adobe Systems, Incorporated, laquelle pourrait être déposée dans certaines juridictions. La notice suivante est applicable à SunForum 3.2 : Copyright DATA CONNECTION LIMITED 2001 Copyright TELES AG 2001 DATA CONNECTION® est une marque déposée de DATA CONNECTION LIMITED aux Etats-Unis et dans d'autres pays.

L'interface d'utilisation graphique OPEN LOOK et Sun™ a été développée par Sun Microsystems, Inc. pour ses utilisateurs et licenciés. Sun reconnaît les efforts de pionniers de Xerox pour la recherche et le développement du concept des interfaces d'utilisation visuelle ou graphique pour l'industrie de l'informatique. Sun détient une licence non exclusive de Xerox sur l'interface d'utilisation graphique Xerox, cette licence couvrant également les licenciés de Sun qui mettent en place l'interface d'utilisation graphique OPEN LOOK et qui en outre se conforment aux licences écrites de Sun.

CETTE PUBLICATION EST FOURNIE "EN L'ETAT" ET AUCUNE GARANTIE, EXPRESSE OU IMPLICITE, N'EST ACCORDEE, Y COMPRIS DES GARANTIES CONCERNANT LA VALEUR MARCHANDE, L'APTITUDE DE LA PUBLICATION A REpondre A UNE UTILISATION PARTICULIERE, OU LE FAIT QU'ELLE NE SOIT PAS CONTREFAISANTE DE PRODUIT DE TIERS. CE DENI DE GARANTIE NE S'APPLIQUERAIT PAS, DANS LA MESURE OU IL SERAIT TENU JURIDIQUEMENT NUL ET NON AVENU.



# Contents

---

**Preface xi**

**1. Introduction to SunForum 1**

SunForum Features 1

Online Help 2

**2. Using SunForum 3**

SunForum Basics 3

▼ To Start the SunForum Software 3

SunForum Menus 5

Using Directories 9

▼ To Change Your Directory Information 9

▼ To Log In to a Directory Server 10

▼ To Log Out From a Directory Server 10

▼ To Refresh the Directory List 10

▼ To Automatically Log In to a Directory Server at Startup 10

▼ To Remove Your Name From the Directory Server 11

▼ To Call a User in the Directory List 11

▼ To Call a User on a Directory Server Using an Email Address 11

Using the SunForum Software 12

|  |           |
|--|-----------|
| Using the SunForum Audio and Video                               | 16        |
| Using the SunForum Whiteboard                                    | 24        |
| ▼ To Select a Whiteboard Mode                                    | 24        |
| ▼ To Start the Whiteboard  | 25        |
| <b>3. SunForum Phone</b>   | <b>37</b> |
| Starting the SunForum Phone                                      | 37        |
| SunForum Phone Menus   | 39        |
| Using the SunForum Phone   | 41        |
| My Video   | 43        |
| Audio and Video Device Settings                                  | 44        |
| Media Configuration Wizard                                       | 45        |
| Preferences  | 46        |
| <b>4. Configuring Gateway Software</b>                           | <b>47</b> |
| Overview   | 47        |
| Gateway Configuration File                                       | 47        |
| Using SunForum Phone Gateway                                     | 49        |
| <b>5. SunForum on a Sun Ray System</b>                           | <b>51</b> |
| Sun Ray Requirements   | 51        |
| Sun Gatekeeper Software  | 52        |
| <b>6. Technical Information</b>                                  | <b>55</b> |
| SunForum Architecture  | 55        |
| SunForum's Conferencing Topology                                 | 56        |
| SunForum's Whiteboard and Compatibility Mode                     | 57        |
| Using the SunForum Software Through a Network Security Mechanism | 58        |
| Using TrueType Fonts With SunForum Software                      | 59        |
| Calling Into a Multipoint Control Unit                           | 59        |

Calling Into Password-Protected Conferences 60

Optimizing Video Display 60

Solving Color Problems 60

SunForum Software Support 61



# Figures

---

- FIGURE 2-1 My Information Window 4
- FIGURE 2-2 SunForum 3.2 Conference Manager 5
- FIGURE 2-3 Conference Manager Audio and Video Icons 17
- FIGURE 2-4 SunForum 3.2 Whiteboard 25
- FIGURE 2-5 Whiteboard Tool Panel 26
- FIGURE 2-6 Whiteboard Options Button 27
- FIGURE 2-7 Whiteboard Options Panel 27
- FIGURE 2-8 Rubber Stamps Button 32
- FIGURE 2-9 Whiteboard Stamps Window 32
- FIGURE 2-10 New Page Button 34
- FIGURE 2-11 Print Button 35
- FIGURE 3-1 SunForum Phone 38
- FIGURE 3-2 Placing a Call 42
- FIGURE 3-3 SunForum Phone Preferences Window 46
- FIGURE 4-1 SunForum Phone GUI in Gateway PBX Mode 48
- FIGURE 4-2 Gateway Network Example of Systems Running SunForum 3.2 49
- FIGURE 4-3 Gateway Mode 50
- FIGURE 6-1 T.120 Conference Hierarchy 57



# Tables

---

|           |                                  |    |
|-----------|----------------------------------|----|
| TABLE 2-1 | Call Menu                        | 6  |
| TABLE 2-2 | View Menu                        | 6  |
| TABLE 2-3 | Tools Menu                       | 7  |
| TABLE 2-4 | Options Menu                     | 8  |
| TABLE 2-5 | Audio and Video Options          | 18 |
| TABLE 2-6 | Audio and Video Device Options   | 19 |
| TABLE 2-7 | Whiteboard Menu Bar Descriptions | 26 |
| TABLE 3-1 | Call Menu                        | 39 |
| TABLE 3-2 | Controls Menu                    | 40 |
| TABLE 3-3 | Address Book Menu                | 40 |
| TABLE 3-4 | Audio and Video Settings         | 43 |
| TABLE 3-5 | Audio and Video Device Options   | 44 |
| TABLE 3-6 | Media Configuration Wizard       | 45 |
| TABLE 3-7 | SunForum Phone Preferences       | 46 |



# Preface

---

This manual describes how to install and use the SunForum™ collaboration software with your Sun™ system. It is for users who want to collaborate over intranets and the internet with both UNIX® and PC-based participants through data conferencing.

---

## How This Book Is Organized

Chapter 1 describes the SunForum product.

Chapter 2 describes how to use the SunForum product, including audio and video features and the SunForum Whiteboard.

Chapter 3 describes the SunForum 3.2 phone feature.

Chapter 4 describes the SunForum gateway access.

Chapter 5 describes using SunForum on a Sun Ray™ system.

Chapter 6 provides technical information about the SunForum software.

---

# Using UNIX Commands

This document does not contain information on basic UNIX commands and procedures such as shutting down the system, booting the system, and configuring devices.

See one or more of the following for this information:

- *Solaris Handbook for Sun Peripherals*
- AnswerBook2™ online documentation for the Solaris™ 2.x operating environment
- Other software documentation that you received with your system

---

# Typographic Conventions

| Typeface         | Meaning   | Examples  |
|------------------|---|---|
| AaBbCc123        | The names of commands, files, and directories; on-screen computer output.   | Edit your <code>.login</code> file.<br>Use <code>ls -a</code> to list all files.<br>% You have mail.  |
| <b>AaBbCc123</b> | What you type, when contrasted with on-screen computer output.  | % <b>su</b><br>Password:  |
| <i>AaBbCc123</i> | Book titles, new words, or terms; words to be emphasized; command-line variable: replace with a real name or value. | Read Chapter 6 in the <i>User's Guide</i> .<br>These are called <i>class</i> options.<br>You <i>must</i> be root to do this.<br>To delete a file, type <code>rm filename</code> . |

---

## Shell Prompts

| Shell                                 | Prompt |
|---------------------------------------|--------|
| C shell                               | %      |
| C shell superuser                     | #      |
| Bourne shell and Korn shell           | \$     |
| Bourne shell and Korn shell superuser | #      |

---

## Accessing Sun Documentation Online

The `docs.sun.comsm` web site enables you to access a select group of Sun technical documentation on the Web. You can browse the `docs.sun.com` archive or search for a specific book title or subject at:

`http://docs.sun.com`

---

## Ordering Sun Documentation

Fatbrain.com, an Internet professional bookstore, stocks select product documentation from Sun Microsystems, Inc.

For a list of documents and how to order them, visit the Sun Documentation Center on Fatbrain.com at:

`http://www.fatbrain.com/documentation/sun`

---

# Sun Welcomes Your Comments

Sun is interested in improving its documentation and welcomes your comments and suggestions. You can email your comments to Sun at:

`docfeedback@sun.com`

Please include the part number (816-1114-10) of your document in the subject line of your email.

# Introduction to SunForum

---

SunForum 3.2 software is a conferencing product for Sun computer systems. It is based on the T.120 and H.323 standards, which enables your Sun system to conference over intranets and the Internet with other T.120 and H.323 products.

---

## SunForum Features

SunForum 3.2 software features:

- View and control applications shared from other UNIX or PC machines that are based on the T.120 protocol
- Share local Solaris applications, which can be viewed and controlled by any conference participant
- Exchange ideas and data using the whiteboard, clipboard, chat, and file transfer facilities
- Use audio and video communications via the H.323 protocol
- DTMF tone generation, in-band and out-of-band through H.245 protocol
- Testing and workarounds for ambiguously specified Voice-over IP (VoIP) and H.323 equipment
- New SunForum Phone GUI
- Ability to automatically place calls through a gateway
- Sun Gatekeeper
- Lightweight Directory Access Protocol (LDAP) server configuration tool
- G.729a audio encoding

---

# Online Help

You can read information about the SunForum software online by accessing help from the Help menu located on any SunForum menu bar.

# Using SunForum

---

This chapter contains the following topics:

- “SunForum Basics” on page 3
- “Using Directories” on page 9
- “Using the SunForum Software” on page 12
- “Using the SunForum Audio and Video” on page 16
- “Using the SunForum Whiteboard” on page 24

---

## SunForum Basics

### ▼ To Start the SunForum Software

- **After installing SunForum 3.2 software packages, type the following at your system prompt:**

```
% sunforum
```

---

**Note** – If the SunForum directory is not set in your path, type the correct path name (for example, /opt/SUNWdat/bin/sunforum).

---

The SunForum conference manager is displayed. When you start SunForum for the first time, however, the My Information window is displayed.



*(new image that shows SunForum Name and SunForum Number is required)*

FIGURE 2-1 My Information Window

- **Type your name and email address in the My Information window.**

---

**Note** – You *must* type your name and email address. You cannot collaborate unless this minimum information is entered.

---

The next time you start the SunForum software, the My Information window will not display automatically. However, you can change the information in the My Information window anytime by choosing Call ► Change My Information to open the information window.

When completing the My Information window, the Configuration Wizard window is displayed for configuring audio/video.

When complete, the SunForum conference manager is displayed as the active window.




FIGURE 2-2 SunForum 3.2 Conference Manager

---

## SunForum Menus

There are five menus on the SunForum menu bar: Call, View, Tools, Options, and Help.

---

**Note** – You can also use the SunForum conference manager buttons to access most of the functions in the Call, View, and Tools menus. See “Using the SunForum Software” for more information.

---

# Call Menu

TABLE 2-1 Call Menu

| Menu                       | Description   |
|----------------------------|---|
| Place Call                 | To place a call to an indicated address. You can also click the Call button.              |
| Stop Placing Call          | To cancel an in-progress call request.  |
| Host Conference            | To start a conference.  |
| Hang Up                    | To end your call. (Same as clicking the Hang Up button.)                                  |
| Do Not Disturb             | To block incoming calls. You may, however, call out.                                      |
| Create SpeedDial           | To create speed dial files for use in your address book or for exchange with other users. |
| Run In Background          | To allow SunForum to continue running in the background when you exit.                    |
| Log On To Directory Server | To log in to a directory server. You will be prompted for the server name.                |
| Change My Information      | To make changes to your profile information.  |
| <i>Address listing</i>     | To call recently accessed addresses.  |
| Exit                       | To exit or place in background the current SunForum session.                              |

# View Menu

Use the View buttons to change these listings viewed in the SunForum conference manager.

TABLE 2-2 View Menu

| Menu Item     | Description   |
|---------------|---|
| Compact View  | To turn the Conference Manager into menu bar.   |
| Always On Top | To cause the Conference Manager window to always be on top.   |
| Directory     | To view the directory server. It lists who you can conference with.   |
| Address Book  | To display addresses that you have conferenced with and added to your address book.   |
| Call Status   | Use during a call to view the status of conference participants and the status of the application sharing, whiteboard, and chatting features. |

**TABLE 2-2** View Menu (*Continued*)

| Menu Item         | Description  |
|-------------------|--|
| History           | To list the status of received calls.  |
| Refresh Directory | To query the directory server for an immediate update of the directory listings. |
| Call Information  | To view audio/video bandwidth usage in the current call.                         |

**Note** – To remove an item from the Address Book and History lists, select the item and press the Delete key.

## Tools Menu

**TABLE 2-3** Tools Menu

| Menu Item              | Description  |
|------------------------|--|
| Switch Audio and Video | To switch audio and video to another participant. Present only while in a conference.  |
| Video                  | To select video windows to be displayed.   |
| Configuration Wizard   | To start the Configuration Wizard program.   |
| Share Application      | To share your applications with others on the call. A submenu lists the shareable applications you have running on your desktop.   |
| Share                  | To select an application window on your desktop for sharing. (Same as clicking the Share button.)  |
| Unshare                | To unshare the application. (Same as clicking the Unshare button.)   |
| Collaborate            | To shift a shared application from view-only to collaborate. When you collaborate an application, you enable others to take control of the application. (Same as clicking the Collaborate button.) |
| Send File              | To select a file to send to everyone in the conference. (Same as clicking the Send button.)  |
| Cancel All Sends       | To cancel sending of files.  |
| Cancel All Receives    | To cancel receipt of files.  |
| Shared Desktop Viewer  | To show an overview of all user desktops and the location of shared applications.  |

**TABLE 2-3** Tools Menu (*Continued*)

| <b>Menu Item</b> | <b>Description</b>  |
|------------------|---|
| Whiteboard       | To start the whiteboard graphical application. The whiteboard automatically starts on other user systems in the conference. (Same as clicking the Whiteboard button.) |
| Chat             | To start the chat application. The chat window automatically starts on other user systems in the conference. (Same as clicking the Chat button.)                      |
| Share Clipboard  | To copy and paste clipboard data between systems.   |

## Options Menu

**TABLE 2-4** Options Menu

| <b>Menu Item</b>            | <b>Description</b>   |
|-----------------------------|--|
| Call Settings               | To configure SunForum options for handling calls.  |
| Tool Settings               | To configure general SunForum options.   |
| Audio/Video Settings        | To configure audio/video conference attributes.  |
| Audio/Video Device Settings | To configure the audio input and output devices and video input device, including the Sun Ray and Sun 1394 Camera. |

## Help Menu

You can access help from the Help menu, located on the SunForum menu bar. Choose Help ► Help Topics for online SunForum information.

---

**Note** – The Help Topics menu is on each of the SunForum window menu bars.

---

---

# Using Directories

To setup your directory entry, you must specify your own details, including name, location, and email address. You are prompted for these details the first time you run SunForum. You can choose whether to list these details for access by everyone; if you do not, then only those people who know your email address will be able to call you via the directory.

This section contains the following topics:

- To Change Your Directory Information
- To Log In to a Directory Server
- To Refresh the Directory List
- To Automatically Log In to a Directory Server at Startup
- To Remove Your Name From the Directory Server
- To Call a User in the Directory List
- To Call a User on a Directory Server Using an Email Address

## ▼ To Change Your Directory Information

### 1. Choose Call ► Change My Information.

### 2. Fill in the following fields:

- **First Name and Last Name.** This is the name used to identify you in a conference.
- **E-mail address.** This is used to identify you when you are logging in to a directory server.
- **SunForum Name and SunForum Number.** SunForum users, especially those using the product for the first time, need to be aware that the "SunForum Name" and "SunForum Number" need to be unique. The Directory Server currently has no way to otherwise uniquely identify users as they are logged onto the server. Additionally, there is no connection between these entities and a person's system username, office telephone number, and so on. However, users can choose to make their SunForum Name identical to their username, and their SunForum Number identical to their office phone extension, if they wish.

It is important to remember that, when using the "standard" mode of placing a SunForum call, the number used in the call is the SunForum Number as entered in the call recipient's SunForum user information. By contrast, entering a number when placing a call via the gateway will attempt to make a connection over the

local telephone system, if the SunForum system configuration is setup to do so. This distinction is important to remember when placing calls to a recipient whose SunForum and office telephone numbers are identical.

- **Category.** This is used by servers to narrow down the list of names when querying or choosing a directory server.

**3. Change the details as required and click OK.**

## ▼ To Log In to a Directory Server

1. **To view the directory listing, choose Call ► Log On To Directory Server.**
2. **Type the name of the directory server you want to log in to and click OK.**

When SunForum has successfully logged in to the directory server, the server is automatically queried for other users also logged in to that directory.

## ▼ To Log Out From a Directory Server

- **To log out from a directory server, choose Call ► Log Off From Directory Server.**

---

**Note** – You can configure an LDAP server as a SunForum directory server. To do this, refer to the SunForum 3.2 Help for these system administrator procedures.

---

## ▼ To Refresh the Directory List

- **Choose View ► Refresh Directory.**

This option can be selected only when the directory list is displayed.

## ▼ To Automatically Log In to a Directory Server at Startup

1. **Choose Call ► Change My information.**
2. **Select “At startup, log on to the directory server.”**
3. **Specify the directory server name in the Server Name field.**

4. **Type the name of the directory server you want to log in to in the Server Name field.**

The next time you start SunForum, it will log in to the directory server you specified.

## ▼ To Remove Your Name From the Directory Server

1. **Choose Call ► Change My Information.**

2. **Select “Do not list my name when logged on to the directory server.”**

The next time you log in to a directory server, your name and details will not be visible to users browsing the directory.

If you are currently logged in and your name is displayed when you select this option, SunForum automatically updates your entry at the directory server so that your name is not displayed.

## ▼ To Call a User in the Directory List

To call a user shown in the directory list, double-click that entry in the directory view.

---

**Note** – If “Add to address book” in the Place Call window (Call ► Place Call) is selected, any users you call via the directory list will be added to the address book list.

---

## ▼ To Call a User on a Directory Server Using an Email Address

The SunForum software enables you to call a user who is logged in to a directory server by specifying the user’s email address.

- **Type the name of the directory server the user is logged in to and the user email address, separated by a slash (/).**

The SunForum software queries the specified directory server for a user with the email address you entered. If the user is logged in to the directory server, SunForum tries to start a call with them.

---

# Using the SunForum Software

Refer to the SunForum conference manager as you read the procedures in this section.

This section contains the following topics:

- Making a Call
- Sharing Applications

## Making a Call

### ▼ To Make a Quick Connection

1. **Choose View ► Address Book, or click the Address Book button.**
2. **Double-click on the address book entry that you want to connect to.**

You can also simply click the Directory or History view buttons and double-click the entry you want to connect to.

### ▼ To Connect Manually

1. **Choose Call ► Place Call, or click the Call button.**

The Place Call window is displayed. The Place Call window enables you to join a conference.

2. **Type the address with which you want to conference.**

In the Place Call window, you can add the address you are calling to your Address Book. You can also specify a named meeting to join (for example, if you are calling a conference server).

3. **Click OK.**

The view will shift to Call Status if the connection is made, or a prompt will inform you why the attempt was unsuccessful.

### ▼ To End a Connection

- **Choose Call ► Hang Up, or click the Hang Up button.**

This ends your participation in a conference.

---

**Note** – When you hang up, you can also disconnect others from the conference. This includes all the participants you invited into the conference, or anyone who called you. If you initiated the conference, the whole conference will be terminated. You will get a warning message if you are about to disconnect others by hanging up.

---

---

**Note** – You can also place calls through a gateway, see Chapter 4 “Configuring Gateway Software.”

---

## Sharing Applications

### ▼ To Share Applications

When you are using the SunForum software, the applications on your entire desktop screen can be shared with other conference participants. This results in the following:

- If a controlling user within a SunForum conference moves an application window on their desktop, it is actually moved on the host desktop. Other applications on the host desktop may obscure the window being shared. If a portion of the shared application window is obscured on the host desktop, that same portion is also obscured on the controlling user’s desktop.
- Sun and PC desktops in a SunForum conference may have different desktop screen sizes. When controlling users move shared windows around on their desktop, the windows may move outside the viewing area of a user in the conference with a smaller desktop screen. A participant with a smaller desktop screen can move (scroll) the active (view) region of the screen by moving the mouse pointer to that area of the desktop where the entire application can be viewed. (To set the scrolling feature, choose Tools ► Options from the SunForum conference manager.)

**1. While in a conference call, choose Tools ► Share, or click the Share button.**

Or, choose Tools ► Share Application to select the application you want to share.

**2. Place your mouse pointer (now a hand symbol) over the desktop application window you want to share.**

**3. Click anywhere in that application window.**

All conference participants can now see that application on their system as if it were running locally. SunForum can share almost any application, including terminal windows, word processors, and CAD design packages. Exceptions include SunForum and applications using certain X extensions that are not supported.

---

**Note** – The window is labeled with the name of the user who shared the application. At this point, only that person can control it; others can only view the output on their desktop.

---

## ▼ To Unshare Applications

1. **Choose Tools ► Unshare, or double-click Unshare, to stop sharing the application.**
2. **Click on the application window that was being shared.**

Now, only you can view and control that application.

## ▼ To Collaborate Applications

Once an application is being shared, the Collaborate button is activated and you can open the application to conference participants for collaborative use.

1. **Share an application (see To Share Applications).**
2. **Choose Tools ► Collaborate, or click Collaborate.**

The shared application that was view-only by the conference participants is now open for collaboration.

When you collaborate your shared application, other conference participants can take control. For a conference participant to take control of the shared application, they only need to click on that application on their desktop.

---

**Note** – When another conference participant clicks the shared application window and is then in control of it, that person effectively take over your mouse and keyboard. Only one user can be in control at a time. Any other user, including the host, can gain control by just clicking the mouse.

---

- **To stop collaborating, click Collaborate again.**

The shared application is returned to view-only for the conference participants.

## ▼ To Transfer Files

1. **Choose Tools ► Send File, or click Send File.**

The Select a File to Send window is displayed.

2. **Go to the directory and select the file you want to send.**

### 3. Click OK.

The file is sent to all the participants in the conference.

Files sent to you by other conference participants are received automatically. While the file is being received, another window shows the progress of the transfer. When the transfer is complete, the file is saved. The default directory for saving files is `/tmp`. To change the default directory where files are saved, choose **Options ► Tools Settings**.

## ▼ To Chat

### 1. Choose **Tools ► Chat**, or click the **Chat** button to start the chat application.

This also automatically starts the chat application on other user systems in the conference.

### 2. Select the recipient of your message.

- To send to all participants, choose **Send to ► Everyone** in conference.
- To send to a single participant, choose **Send to ► user name**.

The names of those conference participants who are running chat are listed in the **Send to** menu.

### 3. Type your message in the message field and press **Return**.

The message is displayed in your chat window and on the other participants' chat windows.

You can list the date, time, and name with the message. To do this, click **View** on the **Chat** menu bar and select or deselect your choice.

You can save chat sessions to a file as a record of the conference. You are prompted to do so when you exit the **Chat** window.

---

**Note** – Though other conferencing products may have T.120 text chatting capability, they may not necessarily work with SunForum chat. Check the chatting status in the SunForum conference manager to see who is running chat.

---

## ▼ To Transfer Data Using the Shared Clipboard

### 1. Ensure that **Shared Clipboard** is enabled on both systems.

### 2. Choose **Tools ► Shared Clipboard**.

The **Shared Clipboard** menu item should be active (checked).

---

**Note** – To automatically enable **Shared Clipboard**, choose **Tools ► Options**.

---

3. Select text from an application (for example, a Command Tool) on one system.
4. Choose Edit ► Copy.
5. In an application (for example, a text editor) on another system, choose Edit ► Paste.

---

## Using the SunForum Audio and Video

The H.323 audio and video communications protocol is the standard for audio/video conferencing. SunForum conforms to the H.323 standard.

This section contains the following topics:

- Types of Audio/Video Conferences
- Configuring Audio and Video Capabilities
- To Set Audio/Video Options
- To Set Audio/Video Device Options
- Controlling Audio Within the Conference
- Controlling Your Video Image Over a Conference
- Controlling Video Image Within a Multipoint Conference
- Controlling Video Within a Point-To-Point Conference

## Types of Audio/Video Conferences

Conferencing products may provide one of three different levels of audio/video support.

- *Multipoint* - You can see and hear many people in the call at the same time. Each person's video image appears in a separate window, and the audio information from each person is mixed together so that you hear a single audio channel including everyone's voice.
- *Point-to-point* - You can see and hear one other person in the call at a time, and can switch from one to another.
- *No audio/video* - You cannot see or hear other people in the conference. Users of conferencing products that do not support audio/video often set up a telephone-based conference call in parallel with the SunForum conference.

SunForum provides multipoint support, but can also operate in point-to-point mode or without audio/video to support conferences with other products:

- If everyone in the conference is using a product that supports multipoint audio/video, you can use either multipoint or point-to-point. (You may prefer to use point-to-point if people are familiar with products that operate only in this mode.)
- If some people are using a product that supports only point-to-point audio/video, you should use point-to-point. SunForum can be configured to force a conference to use point-to-point thus insuring that the products that only support point-to-point can establish audio/video links.
- Anyone who is using a product that does not support audio/video can still participate in the conference, but will not be able to see or hear other people. You can still use audio/video to communicate with anyone in the conference who has support for it.

When you start a call to another person, SunForum initially creates a point-to-point link for audio/video support regardless of the capabilities of the other product. Should a third person join the conference, their capabilities will determine if the conference becomes a multipoint conference or remains a point-to-point conference. Once a conference has become a multipoint conference, products that do not support multipoint will not be able to establish an audio/video link in the conference.

If you want to start a conference explicitly in point-to-point mode, you can specify this in the Audio/Video Settings dialog box. See [To Set Audio/Video Device Options](#) for more information.

In the current call window, the audio/video icons indicate an audio/video link to a participant in the conference.

| Name                 | Sharing       | Whiteboard | Chat | Audio   | Video   |
|----------------------|---------------|------------|------|---|---|
| mconf (MPCS)         | Not available | No         | No   |  |  |
| Robert Bartruff      | Not sharing   | No         | No   |  |  |
| mconf (T.120 Server) | Not available | No         | No   |  |  |

**FIGURE 2-3** Conference Manager Audio and Video Icons

# Configuring Audio and Video Capabilities

## ▼ To Set Audio/Video Options

### ● Choose Options ► Audio/Video Settings.

Or, choose View ► Audio/Video Settings in your video display window or the video display windows of others if you are in a conference.

TABLE 2-5 Audio and Video Options

| Menu Item                                  | Description   |
|--|---|
| Use point-to-point Audio/Video connections | This option allows you to only use point-to-point connections for your audio/video conferences. This guarantees that users who only support point-to-point will be able to utilize Audio and Video as part of the conference.   |
| Send image size                            | Specify the size of your video image as it appears to other people. This also determines the size of the My Video window on your screen. The range of window sizes that you can use depends on the capabilities of the conferencing products being used by other people. If you are already in a conference, one or more of these options may be grayed if other people are using conferencing products that cannot support them. You may find that the window size changes when you start a call, or when another person joins or leaves the conference. This is because another person may not be able to use the size that you originally selected; SunForum cooperates with the other conferencing products to select the best compromise between the requirements of everyone currently in the conference. |
| Default video magnification                | This option specifies the default magnification (100% - 400%) used to display video on your system.   |
| I prefer to receive...                     | This option allows you to tune the picture quality of the video images of other people as they appear on your screen.<br>- Move the slider towards Faster Video to view the video with more updates per second. This gives a smoother display, but reduces the resolution of the image.<br>- Move the slider towards Better Quality to view the video with higher resolution. This gives a better-quality video image, but may mean that the video appears less smooth.   |

**TABLE 2-5** Audio and Video Options (*Continued*)

| Menu Item         | Description   |
|-------------------|---|
| Connection speed  | Select the option that best describes the network over which you are using SunForum 3.2.  |
| Echo suppression  | If selected, SunForum 3.2 disables your microphone when it is playing back audio. Also called half-duplex, this is useful when using a speaker and not a headset. |
| Auto Gain Control | If selected, SunForum 3.2 will automatically adjust the sensitivity of your microphone based on the input level.  |

## ▼ To Set Audio/Video Device Options

- **Choose Options ► Audio/Video Device Settings.**

**TABLE 2-6** Audio and Video Device Options

| Menu Item    | Description   |
|--------------|---|
| Audio Device | Allows you to choose the audio device to use for conferencing and the attributes associated with that device. First you select the audio device you want to use from the menu and then you push the “Settings” button to configure the device specific attributes. Each device is a unique attribute that can be configured.  |
| Video Device | Allows you to choose the video device to use for conferencing and the attributes associated with that device. One choice is “None” for systems without video capture capabilities or for those who are capable but choose to disable it. First you select the video device you want to use from the menu and then you push the “Settings” button to configure the device specific attributes. Each device is a unique attribute that can be configured. |

## Using the Sun 1394 Camera Snap Feature

You can snap a video image directly from the camera with the Sun 1394 Camera. This allows you to capture an image at any location within a 3.0 meter range (1394 cable length) away from your workstation. This feature is activated through SunForum (see “Capturing and Copying Video Images” on page 29).

# Controlling Audio Within the Conference

You can adjust your own audio and adjust the audio you receive from the conference participants.

## To Adjust Your Audio Over a Conference

The checkbox to the left of the Conference Manager Microphone icon indicates whether your audio is being played to other people in the call.

- To start or stop playing your audio to other people in the call, click on the checkbox to the left of the icon.
  - To control the output level of your audio, move the slider to the right to make your audio louder, or to the left to make it quieter. This is important in a multipoint conference, where this slider determines the volume of your audio relative to other people's audio.
  - If you are using point-to-point audio/video, only the person that you are currently switched to will be able to hear you. To switch to a different person in the call, see *Controlling Video Within a Point-To-Point Conference*.

## To Adjust Conference Audio on Your Computer

The checkbox to the left of the Speaker icon indicates whether other participant's audio is being played on your computer.

- To start or stop listening to other people in the call, click on the checkbox to the left of the icon.
- To control the volume, move the slider to the right to increase the volume, or to the left to decrease it.
- If you are using point-to-point audio/video, you will hear only the person that you are currently switched to. To switch to a different person in the call, see *Controlling Video Within a Point-To-Point Conference*.

## Controlling Your Video Image Over a Conference

Before starting a call using video, you can check the video image of yourself that will appear on other participant's screens (for example to make sure that the camera on your system is aligned correctly). The video image appears on your screen in a window with the title *My Video*. You can show or hide the *My Video* window at any time.

## ▼ To Control Your Video Image Before a Conference

- **Choose Tools ► Video ► Display My Video.**

You can also hide the window by closing it. Prior to entering a call you will see the message `Not Sending` beneath the My Video window.

---

**Note** – SunForum 3.2 software enables you to zoom your video display window.

---

## To Control Your Video Image During a Conference

Once in a call, a button is displayed in addition to the status message at the bottom of the My Video window. The status message reflects the current state of video transmission. The button is used to change that state as follows:

- If the video status is “Sending”, the Pause button is shown. Click on this button to pause the video display. When you pause the display, a “freeze frame” image appears in the window and the status message becomes “Paused.”
- If video status is “Paused”, the Play button is shown. Click on this button to activate the video display. When you activate the display, video transmission is restarted and the status message becomes “Sending”.

Instead of the Pause/Play buttons in the window, you can use the Pause or Play option that appears in the View menu of this window. These options only appear when in a call.

You can control whether your video image is automatically sent to other people as soon as you start a call; see [To Set Audio/Video Device Options](#) for more information.

## Controlling Video Image Within a Multipoint Conference

If you are using multipoint audio/video, a video image of each person in the call is displayed automatically when he or she starts sending video.

- Each participant’s image is displayed in a separate window, with the participant’s name as the window title. As other people join or leave the call, new windows appear or existing windows disappear.
- You can choose which of these windows are displayed on your screen.

## ▼ To Control Video Image Within a Multipoint Conference

### ● Choose Tools ► Video ► Display Others.

Click on an entry for the window you want to display or hide. Alternatively, you can hide a displayed window by closing the window using the system menu.

At the bottom of each of these windows, a button indicates whether the video is being displayed, as follows:

- If the video status is “Receiving”, the Pause button is shown. Click on this button to pause the video display. When you pause the display, a “freeze frame” image appears in the window and the status message becomes “Paused”.
- If video status is “Paused”, the Play button is shown. Click on this button to activate the video display. When you activate the display, video transmission is restarted and the status message becomes “Receiving”.

You can control whether you automatically display video images of other people as soon as they start sending video; see *To Set Audio/Video Options* for more information. If you do not display these images, the window for a remote user on your screen remains blank until you use the Play button to start the video display.

Instead of the Pause/Play buttons in the window, you can use the Pause or Play option that appears in the View menu of this window.

---

**Note** – The window size used for other people’s video is determined by the sender’s conferencing product and capabilities.

---

## Controlling Video Within a Point-To-Point Conference

In point-to-point audio/video, you can see and hear only one other person in the conference at a time. You can switch between different people in the conference; if you switch to a different person, the person you were previously seeing and hearing remains in the conference but is not switched to anyone.

---

**Note** – The switch attempt will fail if you try to switch to a person who is already switched to someone else.

---

## ▼ To Switch to Another Person

- **Choose from the Tools ► Switch Audio and Video.**

This displays a list of people that you can switch to, including the person you are currently switched to (with a selection marker next to that person's name). The list does not include people who do not have audio/video support.

- To switch to a different person, click on that person's name in the list.
- To “switch out” so that you remain in the conference but are no longer switched to anyone, click on the name of the person you are currently switched to (the name with the selection marker next to it).

The Switch Audio and Video menu item only appears if you are in a conference with more than one audio/video capable person and are using point-to-point connections.

## Displaying Remote Video in a Point-To-Point Conference

If you are using point-to-point audio/video, the Remote Video window displays a video image of the person you are currently switched to (if any).

- To switch to a different person in the call, see *Controlling Video Within a Point-To-Point Conference*.
- You can choose whether to display this window on your screen by displaying Remote Video.

## ▼ To Display Remote Video

- **Choose Tools ► Video ► Display Others' Video.**

This displays or stops displaying the window. Alternatively, you can close the window by clicking on the Close button for the window.

---

# Using the SunForum Whiteboard

The SunForum Whiteboard enables all conference participants to exchange ideas and graphics. You do not need to be in a conference, however, to use the whiteboard.

There are two types of whiteboards available through SunForum:

- T.126 mode, which allows you to interoperate with any computer system or appliance using the T.126 protocol, regardless of platform software
- SunForum 1.0 mode, which allows you to interoperate with certain collaboration software running on PCs.

This section contains the following topics:

- To Select a Whiteboard Mode
- To Draw Graphical Objects
- To Use Text Objects
- To Move and Delete Objects
- To Highlight Text and Images
- To Capture (Snap) Video Images
- To Add Screen Captures to the Whiteboard
- To Import Graphics
- To Export Graphics
- To Use the Remote Pointer
- To Use Whiteboard Stamps
- To Copy to the Clipboard
- To Navigate and Organize Pages
- To Add a New Page
- To Zoom the Whiteboard
- To Lock the Whiteboard
- To Save the Whiteboard Contents to a File
- To Print the Whiteboard Contents

## ▼ To Select a Whiteboard Mode

1. **Choose Options ► Tool Settings.**
2. **Choose the desired whiteboard mode: T.126 or SunForum 1.0 mode.**

### 3. Click OK.

---

**Note** – Once you select a whiteboard in the Options window, this whiteboard will open each time you select Whiteboard from either the Tools menu or from the Whiteboard button on the SunForum conference manager. See To Start the Whiteboard.

---

## ▼ To Start the Whiteboard

- **Choose Tools ► Whiteboard, or click the Whiteboard button, from the SunForum conference manager.**

The whiteboard mode you selected in the Options window is displayed. This example shows the SunForum T.126 mode whiteboard.




FIGURE 2-4 SunForum 3.2 Whiteboard



## ▼ To Draw Graphical Objects

### 1. Click the tool type in the whiteboard tool panel.

For example, click freehand pen or choose Tools ► Pen from the menu bar.

### 2. Choose your pen color and line thickness.

#### a. Click the Whiteboard Options button located on the bottom of the whiteboard.



FIGURE 2-6 Whiteboard Options Button

The Whiteboard Options panel is displayed.




FIGURE 2-7 Whiteboard Options Panel

#### b. Choose your pen color and pen width, then click OK.

**3. Click and drag your mouse button to draw the object.**

As you release the mouse button, the object is seen by all other conference participants.

## To Use Text Objects

### Creating Text Objects

- 1. Click the Text tool button, or choose Tools ► Text.**
- 2. Place your mouse pointer in the whiteboard where you want to enter text.**
- 3. Click at that location.**

A text field appears in the whiteboard.
- 4. Enter the text and click OK.**

### Editing Text Objects

- 1. Click the Text tool button, or choose Tool ► Text.**
- 2. Click the text in your whiteboard that you want to edit.**

A text field appears in the whiteboard.
- 3. Edit the text and click OK.**

### Setting the Font and Style of Text Objects

You can set font options in two ways:

- By changing settings in the Whiteboard Options tool before creating a new text object
- By selecting a text object, then changing the settings in the Whiteboard Options tool.
- By selecting a text object, then changing the settings when the text field is visible.

- 1. Click the Whiteboard Option button.**

The Whiteboard Options window is displayed.

2. Click the **Text Font, Text Size, and Text Style** menus and choose the font setting.

---

**Note** – Only a small number of fonts are available to ensure that text objects are able to display on all user systems in the conference.

---

3. Click **OK** on the **Whiteboard Options** window.

## ▼ To Move and Delete Objects

1. Click the **Selector** tool button, or choose **Tools > Selector**.
2. Click the **graphic or text that you want to move or delete**.  
A border is highlighted on the selected object.
  - a. To move the graphic or text, drag it with the mouse pointer to its new position.
  - b. To delete the graphic or text, press **Delete** on your keyboard, or choose **Edit > Delete**.

---

**Note** – If you delete an object by mistake, you can undelete and retrieve the last deletion by choosing **Edit > Undelete**.

---

## ▼ To Highlight Text and Images

1. Click the **Highlight** button, or choose **Tools > Highlighter**.
2. Draw on the whiteboard area you want to highlight.

# Capturing and Copying Video Images

You may snap a camera video image from either the whiteboard tools panel, or from the Sun 1394 Camera snap button, and copy it as an image to the whiteboard.

## ▼ To Capture an Image from the Whiteboard Tools Panel

1. Select the camera video image you wish to capture.
2. Click the **Snap My Video** from the **Whiteboard** tools panel (see FIGURE 2-5), or choose **Tools > Snap My Video** from the **Tools** menu.

The image appears and is copied in the top left corner of the Whiteboard window.

## ▼ To Capture an Image Using the Sun 1394 Camera

1. **Click the Enable Camera button on the whiteboard tools panel (see FIGURE 2-5).**

This enables the Sun 1394 Camera snap button so that each time you press the camera snap button, the image is captured on the Whiteboard.

2. **Focus on the image to be captured and press the Sun 1394 Camera snap button.**

If you do not use the camera snap button for a period of 60 seconds, then the snap button becomes disabled again.

---

**Note** – If you want to disable the snap button on the camera before the timeout period expires, simply press the Escape key.

---

## To Add Screen Captures to the Whiteboard

You can capture the contents of a window, or an area of the desktop, to add to your whiteboard for conferencing.

### Selecting and Capturing a Window

1. **Click the Select window button, or choose Tools ► Select Window.**

The whiteboard becomes an icon and the mouse pointer becomes a hand symbol.

2. **Place the mouse pointer on the window you want to add to your whiteboard.**

3. **Click the window.**

The window is captured and placed in your whiteboard.

### Selecting and Capturing an Area of the Screen

1. **Click the Select window button, or choose Tools ► Select Area.**

The whiteboard becomes an icon and the mouse pointer becomes a pair of crosshairs.

2. **Drag the mouse pointer over the area of your desktop screen that you want to capture.**

The image area is captured and placed in your whiteboard as you release the mouse button.

---

**Note** – Once the image is captured in the whiteboard, you can use the Selector tool to select the image and move or delete it across your whiteboard. See To Move and Delete Objects.

---

## ▼ To Import Graphics

1. **Choose File ► Import.**

The Select a file to import window is displayed.

2. **Specify the file you want to import and click OK.**

The image is added to the current page.

---

**Note** – You need the shareware filter `ghostscript` to import PostScript files into the whiteboard. The location of `ghostscript` must be separately specified in `/etc/opt/SUNWdat/config/system-config` as `Whiteboard.GSPath`.

---

## ▼ To Export Graphics

1. **Choose File ► Export.**

The Export file window is displayed.

2. **Specify the file you want to export.**

3. **Choose an image format from the Save file as type menu.**

4. **Click OK.**

The contents of the current page is written to the file in the selected format.

## ▼ To Use the Remote Pointer

The remote pointer is a pointing hand that everyone in the conference can see. When you have the Select tool enabled, you can click on the pointer and drag it around, so that you can point out areas of interest on the page.

1. **Click the Remote Pointer button, or choose Tools ► Remote Pointer.**

A hand symbol pointer is displayed on your whiteboard.

2. **Click and drag the remote pointer to move to selected areas of interest.**

## ▼ To Use Whiteboard Stamps

The Whiteboard Stamps window offers a number of images you can “stamp” on the whiteboard. These are user configurable. The SunForum software enables you to use bitmap files (such as GIF) in user-defined locations.

---

**Note** – The location is `/etc/opt/SUNWdat/config/dcgx`, listed as `Whiteboard.StampFilename.1` through `Whiteboard.StampFilename.12`. You may have more than 12 stamps, however.

---

1. Click the rubber stamp button.



FIGURE 2-8 Rubber Stamps Button

The Whiteboard Stamps window is displayed.




FIGURE 2-9 Whiteboard Stamps Window

2. **Click on a stamp image and click OK.**

When you place the pointer in the whiteboard, the pointer is a stamp.

3. **Place the stamp pointer in the whiteboard where you want the image to appear and click.**

The stamp image is displayed.

## To Copy to the Clipboard

You can cut and paste to and from a clipboard in two ways:

- Using the quick method to copy text
- Using the Edit commands to cut and paste text and graphics

### Using the Quick Method to Copy Text

1. **Select text in the whiteboard (or another text source window) or from another application.**
2. **Place the mouse pointer in the whiteboard and click the middle mouse button to paste the text selection.**

### Using the Edit Commands

1. **Select the text or object you want to copy.**
2. **Choose Edit ► Cut or Edit ► Copy.**
3. **Go to a new whiteboard page and choose Edit ► Paste.**

### ▼ To Navigate and Organize Pages

- **To navigate pages, use the navigation arrows at the bottom of the whiteboard to change pages; or, use the Edit menu to clear, delete, insert, and to go to specific pages.**
- **To organize pages, choose Edit ► Bring to Front or Edit ► Send to Back to move the current page accordingly.**

## ▼ To Add a New Page

- **Click the new page button or choose Edit ► Insert Page, located in the bottom right corner of the whiteboard.**

A new page is added after the current page.



FIGURE 2-10 New Page Button

---

**Note** – Using the menu to insert a page enables you to place the new page before or after the current page.

---

## ▼ To Zoom the Whiteboard

- **Click the Zoom button, or choose Tools ► Zoom.**

This changes the magnification of the whiteboard contents you are viewing.

## ▼ To Lock the Whiteboard

You can lock the whiteboard so that no one else in the conference can make any changes to the contents.

1. **Click the Lock button, or choose Tools ► Lock.**

After a short delay, either you will have successfully locked the whiteboard (indicated by the lock “down” position), or you will be notified that it could not be locked. You may not be able to lock it because another user in the conference has already locked the whiteboard or is in the middle of an operation that cannot be interrupted.

2. **Click the lock button a second time to release the lock.**

---

**Note** – Locking feature cannot be used in a T.120 whiteboard.

---

▼ To Save the Whiteboard Contents to a File

- Choose File ► Open.

or

- Choose File ► Save (or File ► Save As).

▼ To Print the Whiteboard Contents

- Click the Print button, or choose File ► Print.



FIGURE 2-11 Print Button

In the print window, specify the printer or file name to print to, and which pages you want to print.

---

**Note** – The printer name must be a valid printer device. The SunForum software allows you to also specify a networked printer name.

---



## SunForum Phone

---

This chapter contains the following topics:

- “Starting the SunForum Phone” on page 37
  - “SunForum Phone Menus” on page 39
  - “Using the SunForum Phone” on page 41
  - “My Video” on page 43
  - “Audio and Video Device Settings” on page 44
  - “Media Configuration Wizard” on page 45
  - “Preferences” on page 46
- 

## Starting the SunForum Phone

- After installing SunForum 3.2 software packages, type the following at your system prompt:


```
% phone
```

---

**Note** – If the SunForum directory is not set in your path, type the correct path name (for example, /opt/SUNWdat/bin/phone).

---

The SunForum Phone is displayed (FIGURE 3-1).



**FIGURE 3-1** SunForum Phone

---

**Note** – Once the SunForum Phone displays, you can toggle the SunForum conference manager from the Phone user interface Controls menu. You cannot start the Phone from the SunForum conference manager, however, if SunForum is started first.

---



---

**Note** – The SunForum Phone interface is used for audio and video calls. For data collaboration or advanced settings, you must toggle to the SunForum conference manager interface (see Chapter 2 “Using SunForum”).

---

---

# SunForum Phone Menus

There are four menus on the SunForum Phone menu bar: Call, Controls, Address Book, and Help. The following tables describe each of the Phone menu options.

## Call Menu

---

**Note** – The Place Call menu item and Call button on the Phone interface are disabled until you enter an address in the Call Edit field (FIGURE 3-1).

---

**TABLE 3-1** Call Menu

| Menu                         | Description  |
|------------------------------|--|
| Place Call                   | To place a call to an indicated address. You can also click the Phone Call button. |
| Hang Up                      | To end your call. (Same as clicking the Hang Up button.)                           |
| Change My Information        | To make changes to your SunForum profile information.                              |
| Directory                    | To view the directory server. It lists those with whom you can conference.         |
| <i>List of phone numbers</i> | A history list of the last dialed numbers (lists a maximum of 10 phone numbers)    |
| Exit                         | To exit the SunForum Phone software.   |

# Controls Menu

TABLE 3-2 Controls Menu

| Menu Item                   | Description   |
|-----------------------------|---|
| Volume                      | To increase, decrease, or mute volume.                                      |
| Microphone                  | To toggle the microphone on or off.   |
| Toggle SunForum             | To open and close the SunForum conference manager.                          |
| Audio/Video Device Settings | To select audio and video devices and to configure the settings of each.    |
| Media Config Wizard         | This provides help in configuring your audio and video device settings.     |
| Preferences                 | To set preference conditions for Incoming Calls, Telephone Key, and Cursor. |

# Address Book Menu

The SunForum Phone Address Book menu lists the user's addressbook and addresses not frequently used. The history portion of the Call menu contains a list of the 10 most previously used addresses, however.

TABLE 3-3 Address Book Menu

| Menu Item                | Description  |
|--------------------------|--|
| Add Address              | To add an address to the Address Book. This is only available when a conference participant is selected in the Phone roster, during a conference. This fills the address information for the user. |
| New Address              | To add a new address. This is always available.  |
| Edit Address Book        | This displays a list of addresses in your address book and enables addresses to be created, edited, or deleted.  |
| <i>List of addresses</i> | A list of addresses that are frequently conferenced.   |

There are three types of addresses a user can create in the Add Address and New Address windows:

- Telephone: a telephone number to be used with a gateway
- Network (TCP/IP): a call alias used with a Sun Gatekeeper
- Directory: an LDAP directory to use with the address

# Help Menu

You can access help information from the Help menu located on the SunForum Phone menu bar

- **Choose Help ► Phone Help for online SunForum Phone information.**

or

- **Choose Help ► Popup Help.**

Popup Help toggles Help messages that are displayed underneath the cursor when the cursor is positioned on many of the Phone GUI controls.

---

# Using the SunForum Phone

Once your SunForum Phone is displayed and you have configured the audio and video device settings and phone preferences to your needs (TABLE 3-1 and TABLE 3-2), you are ready to place a call.

## Placing a Call

Besides using the Phone menu bar to place calls, you can use the Phone user interface.

### ▼ To Place a Call Through the Phone Interface

- **Click the phone number you wish to call on the phone interface keypad.**

The number is displayed in the field just above the keypad. Then click the Place Call icon to place the call (FIGURE 3-2).

or

- **Type the phone number, or alias name, from your computer keyboard.**

The number is displayed in the field just above the keypad. Press Return on your keyboard (or click the Place Call icon) to place the call.

Once you have placed the call, an Outgoing Call window displays as it dials the number. You can also cancel the call from the Outgoing Call window.



FIGURE 3-2 Placing a Call

### ▼ To Clear a Number That You Have Entered

- **Clear the number from your keyboard by selecting the entire Call edit field and pressing Delete.**

or

- **Click the Clear button until the number is erased.**

### ▼ To Turn On the Phone Microphone

- **Click the Phone mic button.**

---

**Note** – A computer phone microphone/headset is recommended for each participant in the conference.

---

---

# My Video

You can view your video that is being broadcast over a conference and configure your audio and video settings. To do this:

1. **Double click the My Video button (FIGURE 3-2) next to your name in the Name field. See FIGURE 3-2.**

The My Video window is displayed.

2. **From the My Video menu bar, choose View ► Audio/Video Settings.**

The Audio/Video Settings window is displayed. TABLE 3-4 describes the setting options.

TABLE 3-4 Audio and Video Settings

| Menu Item                                  | Description   |
|--|---|
| Use point-to-point Audio/Video connections | This option allows you to only use point-to-point connections for your audio/video conferences. This guarantees that only users who support point-to-point will be able to utilize Audio and Video as part of the conference.   |
| Send image size                            | Specify the size of your video image as it appears to other people. This also determines the size of the My Video window on your screen. The range of window sizes that you can use depends on the capabilities of the conferencing products being used by other people. If you are already in a conference, one or more of these options might be disabled if other people are using conferencing products that cannot support them. You might find that the window size changes when you start a call, or when another person joins or leaves the conference. This is because another person might not be able to use the size that you originally selected; SunForum cooperates with the other conferencing products to select the best compromise between the requirements of everyone currently in the conference. |
| Default video magnification                | This option specifies the default magnification (100% - 400%) used to display video on your system.   |
| I prefer to receive...                     | This option allows you to tune the picture quality of the video images of other people as they appear on your screen. <ul style="list-style-type: none"><li>- Move the slider towards Faster Video to view the video with more updates per second. This gives a smoother display, but reduces the resolution of the image.</li><li>- Move the slider towards Better Quality to view the video with higher resolution. This gives a better quality video image, but might mean that the video appears less smooth.</li></ul>   |

**TABLE 3-4** Audio and Video Settings (*Continued*)

| <b>Menu Item</b>  | <b>Description</b>  |
|-------------------|---|
| Connection speed  | Select the option that best describes the network over which you are using SunForum 3.2.                                      |
| Echo suppression  | If selected, SunForum 3.2 disables your microphone when it is playing back audio (half-duplex).                               |
| Auto Gain Control | If selected, SunForum 3.2 automatically and continuously adjusts the sensitivity of your microphone based on the input level. |

---

## Audio and Video Device Settings

### ▼ To Set Audio/Video Device Options

- **Choose Controls ► Audio/Video Device Settings from the Phone menu bar.**

**TABLE 3-5** Audio and Video Device Options

| <b>Menu Item</b> | <b>Description</b>  |
|------------------|---|
| Audio Device     | Enables you to choose the audio device to use for conferencing and the attributes associated with that device. First select the audio device you want to use from the menu and then click the “Settings” button to configure the device specific attributes. Each device is a unique attribute that can be configured.  |
| Video Device     | Enables you to choose the video device to use for conferencing and the attributes associated with that device. One choice is “None” for systems without video capture capabilities or for those who are capable but choose to disable it. First select the video device you want to use from the menu and then click the “Settings” button to configure the device-specific attributes. Each device is a unique attribute that can be configured. |

---

# Media Configuration Wizard

The SunForum Phone Configuration Wizard helps you configure your audio and video settings. TABLE 3-6 describes the Configuration Wizard device settings and tests.

- 1. Choose Controls ► Media Configuration Wizard from the Phone menu bar.**  
Be sure to close all other applications that use audio and video.
- 2. Click Next at each window to progress through the configuration pages (TABLE 3-6).**
- 3. Click Finish on the last page when done.**

**TABLE 3-6** Media Configuration Wizard

| Menu Item            | Description  |
|----------------------|--|
| Media Device Setting | Enables you to choose which audio and video device SunForum will use for conferencing and the attributes associated with that device. First select the audio and video device you want to use from the Audio and Video Device menu. Click the “Settings” button to configure the device-specific attributes. Each device is a unique attribute that can be configured. |
| Audio Output         | Enables you to check that your speakers and headphones are working properly. Click the Test button to play test audio and adjust the volume slider accordingly.  |
| Microphone Level     | Enables you to confirm that your microphone is working correctly and automatically adjusts it to an acceptable level.  |

---

**Note** – While in a call, the Media Configuration Wizard is unavailable.

---

# Preferences

The SunForum Phone Preferences window (FIGURE 3-3) enables you to configure incoming calls, telephone key, and cursor action. TABLE 3-7 describes the Preferences configuration window.




FIGURE 3-3 SunForum Phone Preferences Window

- **Choose Controls > Preferences from the Phone menu bar.**

TABLE 3-7 SunForum Phone Preferences

| Menu Item      | Description  |
|----------------|--|
| Incoming Calls | To enable type of ring for incoming calls, to set continuous or number of rings, to set interval of rings in seconds, and to set the ring through your speaker. Ring Through Speaker forces the ringer to play through the external speaker on incoming calls. This enables you to still hear the ringer if a headset is being used. |
| Telephone Key  | Enables you to assign a key which you can use to answer incoming calls. You can select to use either the Control, Alt, Meta keys as your function keys (for example, Alt-F5).  |
| Cursor         | Provides the option in a call address field of blinking, steady, or no cursor action.  |

# Configuring Gateway Software

---

This chapter describes how to configure gateway software in order to place calls over the network using the SunForum Phone.

---

## Overview

The gateway software enables you to connect to a designated server that provides the phone line connections required to place calls over a network when using the SunForum Phone (see Chapter 3 “SunForum Phone”). Once you have updated your gateway configuration file, you can then call the gateway server phone lines that connect your calls over the network.

---

## Gateway Configuration File

To update your gateway configuration file:

- 1. Become superuser in a shell window.**
- 2. Go to the SunForum configuration directory:**

```
# cd /opt/SUNWdat/config
```

- 3. Open the SunForum system configuration file:**

```
# vi system-config
```

**4. Locate the gateway settings portion of the configuration file and type the required information.**

In this example, the server name to be designated as the gateway server is Server 1 and 011# is the gateway prefix that may be required to place the call to a gateway server.

```
!  
! Gateway settings  
!  
H323.CallViaGateway: TRUE  
H323.GatewayName: server1  
H323.GatewayPrefix: 011#
```

**5. Save the file, exit superuser, and start SunForum Phone (see Chapter 3 “SunForum Phone”).**

The SunForum Phone Controls menu now lists Gateway Mode.

**6. Toggle Gateway Mode from the Controls menu.**

The SunForum Phone display changes to the gateway mode (FIGURE 4-1).




**FIGURE 4-1** SunForum Phone GUI in Gateway PBX Mode

---

# Using SunForum Phone Gateway

FIGURE 4-2 shows an example of a networked system accessing a gateway server. This example shows Sun Ultra workstations and Sun Ray systems connected to the network. (For more information on SunForum and Sun Ray systems, see Chapter 5 “SunForum on a Sun Ray System.” Sun Ray systems require Sun Gatekeeper software to place calls over a wide area network.)



**FIGURE 4-2** Gateway Network Example of Systems Running SunForum 3.2

In this example, Sun workstations and Sun Ray systems are running SunForum 3.2 and SunForum Phone. Server 1 is a two-line gateway server and indicates the phone lines required when making your calls to telephones. In order to place a call over the network from your SunForum Phone, you must first dial and connect with the designated gateway server. (Sun Ray systems, as shown, go through the Sun Ray server and Sun Gatekeeper to dial into the network. See “Sun Gatekeeper Software” on page 52.)

To dial your SunForum Phone into a network:

- 1. Start SunForum Phone.**
- 2. Update the SunForum system configuration file.**

See “Gateway Configuration File” on page 47.

### 3. Choose Controls ► Gateway Mode.

The SunForum Phone display changes to the gateway mode.



FIGURE 4-3 Gateway Mode

4. In the Call edit field (FIGURE 4-3), enter the number you are calling.
5. Press Return, or click the Place Call button, to make the connection.

---

**Note** – This is similar to calling the gateway directly by using extension 011# at the dial tone, dialing the phone number (in this example, 46953) using DTMF.

---

## SunForum on a Sun Ray System

---

This chapter contains the following topics:

- “Sun Ray Requirements” on page 51
- “Sun Gatekeeper Software” on page 52

---

### Sun Ray Requirements

Your Sun system server requires Sun Ray Server Software 1.2 to support SunForum 3.2 software. Refer to your Sun Ray system documentation for installation procedures of this software.

If Sun Ray 1.2 software patches for SunForum are available, install these patches instead of the procedure in “Sun Ray Libraries” below.

### Sun Ray Libraries

---

**Note** – The following instruction is only required when adding SunForum support to Sun Ray Server 1.2 software.

---

Two Sun Ray libraries are required for installations using Sun Ray clients. The libraries are: `libutmedia.so` and `libutadmin.so`.

To install these libraries:

- **Copy both libraries from the CD-ROM supplementary directory into the Sun Ray library directory** `/opt/SUNWut/lib/`.

---

# Sun Gatekeeper Software

## Overview

SunForum 3.2 includes a H.323 gatekeeper that is required when using the SunForum software with a Sun Ray system. After installing the `SUNWkeep` package, the gatekeeper option is available. The `SUNWkeep` package is installed with the SunForum 3.2 software (see *SunForum 3.2 Software Installation Guide*).

A *gatekeeper* is software that is used for call control and management of voice, video, and data networks. After the gatekeeper is installed and started, H.323 users (including SunForum users) register with it. IP addresses, along with H.323 aliases (names and numbers) are used; all calls are then routed through this central location.

Though the gatekeeper software is required for using SunForum on Sun Ray systems, it is also required in a Sun workstation conferencing environment when at least one Sun Ray system wishes to join the workstation environment.

The Sun gatekeeper provided with SunForum 3.2 only provides address translation and aliasing with port numbers. For this reason, the daemon is called a “registrar.” (Sun gatekeeper does not support bandwidth management.)

A gatekeeper requires that each registrant have a unique alias or aliases. It is suggested that each SunForum client use a telephone extension, email address, or other unique name.

## Starting Sun Gatekeeper

---

**Note** – Only one gatekeeper is allowed to run in any installation. You can install the package in multiple locations, but only *one* server can start the gatekeeper daemon.

---

1. **Decide which server will start the gatekeeper software.**
2. **Become superuser.**

### 3. Start Sun gatekeeper. Type:

```
# registrar start
```

---

**Note** – If the SunForum directory is not set in your path, type the correct path name (for example, /opt/SUNWkeep/bin/registrar start).

---

## Editing the System Configuration File

The SunForum 3.2 clients are set up for “auto discovery” of the gatekeeper server as a default. This auto discovery uses IP Multicast and may not penetrate routers going across subnets. In this case, you need to specify the gatekeeper by name. To specify the gatekeeper server, you need to edit the configuration file:

1. Become superuser.
2. Go to your system configuration file:

```
# cd /opt/SUNWdat/config/  
# vi system-config
```

### 3. Change the configuration file default settings.

The following example uses “GK-server” as your selected server name.

```
Default setting: for auto discovery  
H323.GKDiscovery: 1  
H323.GKName: None  
  
Change to: for manual gatekeeper specification  
H323.GKDiscover: 2  
H323.GKName: GK-server
```

---

**Note** – If a gatekeeper becomes unavailable (either by system or network failure), incoming calls will fail. You should choose a gatekeeper server to be a reliable machine on a reliable subnet.

---

### 4. To view who is registered in the gatekeeper, type:

```
% registrar -q
```



## Technical Information

---

This chapter contains the following topics:

- “SunForum Architecture” on page 55
- “SunForum’s Conferencing Topology” on page 56
- “SunForum’s Whiteboard and Compatibility Mode” on page 57
- “Using the SunForum Software Through a Network Security Mechanism” on page 58
- “Using TrueType Fonts With SunForum Software” on page 59
- “Calling Into a Multipoint Control Unit” on page 59
- “Calling Into Password-Protected Conferences” on page 60
- “Solving Color Problems” on page 60
- “SunForum Software Support” on page 61

---

## SunForum Architecture

The SunForum architecture is based on the International Telecommunications Union (ITU) protocol standards H.323, which defines a set of multimedia communications and conferencing over packet-based networks. The H.323 architecture includes the foundations for audio (G.7xx standards), video (H.26x standards), and data communications (T.120 family of standards). T.120 contains a series of communication and application protocols and services that provide support for real-time, multipoint data communications.

The G.7xx standards contain G.711, G.723 and G.729 for audio.

The H.26x standards contain the H.261 and H.263 standards for video compression.

The T.120 architecture is a multilayered design, with defined protocols and service definitions between layers. The upper-level layers require the lower-level layers of the architecture to function.

The lower-level layers (T.122 through T.125) specify an application-independent mechanism for providing multipoint data communication services to any application that can use these facilities.

The upper-level layers define protocols for specific conferencing applications, such as T.126 for viewing and annotating still images, T.127 for multipoint file transfer and T.128 for application sharing.

Applications that use these standardized protocols can coexist in the same conference with applications that use proprietary protocols. In fact, SunForum software users can use a mix of standardized and nonstandardized protocols.

---


## SunForum's Conferencing Topology

In a SunForum conference, the topology and hierarchy of the connections is conforming to the topologies for H.323 conferences and T.120 conferences. In a multipoint H.323 conference, one endpoint is the Multipoint Controller, and every other endpoint has a single direct connection to that Multipoint Controller. In a point-to-point H.323 conference, there is no Multipoint Controller, and the two endpoints simply have a direct connection. In the T.120 conference there is a more complicated hierarchal topology, and this determines the behavior of the connections. We will describe this in more detail.

In a T.120 conference, a hierarchy exists where the person starting the conference is at the top and those joining the conference are underneath. Where a caller is in this topology affects the conference connection of those who joined that particular caller in the conference. This is illustrated in the following figure.

In this example,

- If B hangs up, all those that B called are disconnected as well, leaving A and D in the conference
- If D hangs up, only D is disconnected, leaving A, B, and C in the conference
- If A hangs up, the entire conference ends



**FIGURE 6-1** T.120 Conference Hierarchy

The way you create a conference is to establish one system, the conference *host*, for conference participants to call in to. A *star* (as in a star networking protocol) topology is created where anyone except the host can leave the conference independently. (This host can actually be a dedicated conference server machine, supporting several conferences simultaneously.)

---

## SunForum's Whiteboard and Compatibility Mode

There are several types of whiteboards available through SunForum:

- SunForum 1.0 mode, which allows you to interoperate with certain collaboration software running on PCs. This is chosen through the menu system Options ► Tool Settings... ► SunForum 1.0 mode.
- "True T.126" mode, which allows you to interoperate with any computer system or appliance using the T.126 protocol, regardless of platform software. This is chosen by setting the T.126 mode and T.120 buttons in the Options ► Tool Settings... panel.

- "NetMeeting 3.x style T.126" mode, which allows you to interoperate with the NetMeeting 3.x whiteboard. This is chosen by setting the T.126 mode and NetMeeting 3 buttons in the Options ► Tool Settings... panel.

Note that the choice of Compatibility mode in the Options ► Tool Settings... panel affects other areas of SunForum as well. The most visible difference between the two modes is in Application Sharing.

- T.120 mode, is designed to comply to the T.120 standard, and in this mode, SunForum should interoperate with other systems using the T.120 protocol stack. This mode should be used for interoperating with NetMeeting 2.x.
- NetMeeting 3 mode, which allows you to interoperate with certain collaboration software running on PCs (NetMeeting 3.x in particular), and makes Application Sharing resemble that of NetMeeting 3.01.

The selection of compatibility mode is made through the Options->Tool Settings... menu item.

---

## Using the SunForum Software Through a Network Security Mechanism

If you are connected to the internet through a network security mechanism, or *firewall*, (as is usual in most corporate/LAN environments), you can use SunForum software to communicate with others located inside the firewall.

To enable full external communication, the firewall (that is, network security mechanism) needs to be set up to allow communication through certain ports (that is, the ports need to be "opened up"):

- Ensure your workstation has its default gateway set to the internal address of the network security mechanism computer.
- Configure the network security mechanism to enable primary TCP connections over the following IP ports:
  - 389 - for communication with Internet Locator Servers, if this is desired
  - 1503 - for T.120 data, i.e. application sharing, file transfer, whiteboard and chat
  - 1718 (UDP) - for locating H.323 gatekeepers (required only if automatic gatekeeper discovery is used)
  - 1719 (UDP) - for communication with H.323 gatekeepers
  - 1720 (TCP) - for H.323 call setup

- Ensure that the firewall is configured to allow the use of dynamic IP ports (both TCP ports for H.323 call control, and UDP ports for audio and video streams). This may require the use of a special H.323-capable firewall product.
- Configure the firewall to map internal IP addresses to external Internet addresses. [This is not possible with all firewalls. If your firewall cannot do this, you will be able to call out from inside the firewall, but you will not be able to receive incoming calls from computers outside the firewall.]

If you are unsure whether you are connecting to the Internet via a network security mechanism, consult your system administrator or Internet service provider.

---

## Using TrueType Fonts With SunForum Software

SunForum software is designed to take advantage of a TrueType font server if one is installed on your system (or accessible to your system across a local area network). Solaris 2.6 operating environment and subsequent compatible versions support TrueType fonts.

With a TrueType font server installed, SunForum software will have more fonts in common with PC systems, resulting in better quality output and improved performance in sharing sessions involving both UNIX and PC systems.

---

## Calling Into a Multipoint Control Unit

SunForum software supports Multipoint Control Unit (MCU) hosted conferences, and has been tested with some of the MCUs available at the time of this release.

When calling an MCU, specify the address of the MCU as normal. If SunForum software detects that the machine called is currently hosting more than one conference, you will be prompted to specify which conference to join. Also, see “Calling Into Password-Protected Conferences.”

---

## Calling Into Password-Protected Conferences

You cannot create a password-protected conference with SunForum software.

When you call into a conference that has been designated as password-protected, SunForum software will prompt you to specify the password.

Some T.120 implementations incorrectly list conferences as password-protected, even when no password has been specified. In this case, just click OK without specifying a password; the conference will be established as normal.

---

## Optimizing Video Display

For better performance of video displays, increase the shared memory pool size to at least 16 Mbytes. To do this,

1. **Add the following line to the `/etc/system` file:**

```
set shmsys:shminfo_shmmax=16777216
```

2. **Reboot your system.**

---

## Solving Color Problems

If you experience problems with color operations (such as text highlighting) with shared PC applications, try the following:

- If your X Server is running with a Static or DirectColor default visual, switch it to run with PseudoColor or GrayScale. See your X Server documentation for information on how to do this.
- Close any local color-intensive X applications (such as bitmap editors and web browsers) to make more colors available for the SunForum software.

---

# SunForum Software Support

If you have any problems installing or using the SunForum software:

- Refer to the written or online documentation included with the software.
- Read the rest of the online help, especially the `README` page, for a list of known problems with this release.
- If you are unable to find an answer, contact your Sun representative and have the following information available:
  - Your system configuration (system hardware, operating system version, graphics hardware)
  - A complete description of what you were doing when the problem occurred
  - Any core file generated (check the `/opt/SUNWdat` directory)
  - The contents of any error log files generated (look for `hostname.trc1` and `hostname.trc2`, located in the `$HOME/.sunforum/trc` directory)

