Sun Configuration and Service Tracker

version 3.6.0

Customer Installation and Operations Guide



Sun Microsystems, Inc. 500 Eldorado Blvd Broomfield, Colorado 80021 30th June 2006

> Part No. 819-6838-10 Release 1.2

Copyright © 2006 Sun Microsystems, Inc., 4150 Network Circle, Santa Clara, California 95054, U.S.A. All rights reserved.

THIS SOFTWARE DESCRIBED IN THIS DOCUMENT CONTAINS CONFIDENTIAL INFORMATION AND TRADE SECRETS OF SUN MICROSYSTEMS, INC. USE, DISCLOSURE OR REPRODUCTION IS PROHIBITED WITHOUT THE PRIOR EXPRESS WRITTEN PERMISSION OF SUN MICROSYSTEMS, INC.U.S. Government Rights - Commercial software. Government users are subject to the Sun Microsystems, Inc. standard license agreement and applicable provisions of the FAR and its supplements.

Parts of the product may be derived from Berkeley BSD systems, licensed from the University of California. UNIX is a registered trademark in the U.S. and in other countries, exclusively licensed through X/Open Company, Ltd.

Sun, Sun Microsystems, the Sun logo, Java, Solaris, Sun Fire 15K, Sun Fire 12K and Sun Enterprise 10000 are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

Copyright © 2006 Sun Microsystems, Inc., 4150 Network Circle, Santa Clara, California 95054, Etats-Unis. Tous droits réservés.

CE LOGICIEL CONTIENT DES INFORMATIONS CONFIDENTIELLES ET DES SECRETS COMMERCIAUX DE SUN MICROSYSTEMS, INC. SON UTILISATION, SA DIVULGATION ET SA REPRODUCTION SONT INTERDITES SANS L AUTORISATION EXPRESSE, éCRITE ET PRÉALABLE DE SUN MICROSYSTEMS, INC. Droits du gouvernement américain, utilisateurs gouvernementaux - logiciel commercial. Les utilisateurs gouvernementaux sont soumis au contrat de licence standard de Sun Microsystems, Inc., ainsi qu aux dispositions en vigueur de la FAR [(Federal Acquisition Regulations) et des suppléments à celles-ci.

Des parties de ce produit pourront être dérivées des systèmes Berkeley BSD licenciés par l'Université de Californie. UNIX est une marque déposée aux Etats-Unis et dans d'autres pays et licenciée exclusivement par X/Open Company, Ltd.

Sun, Sun Microsystems, le logo Sun, Java, Solaris, Sun Fire 15K, Sun Fire 12K et Sun Enterprise 10000 sont des marques de fabrique ou des marques déposées de Sun Microsystems, Inc. aux Etats-Unis et dans d'autres pays.

LA DOCUMENTATION EST FOURNIE "EN L'ÉTAT" ET TOUTES AUTRES CONDITIONS, DECLARATIONS ET GARANTIES EXPRESSES OU TACITES SONT FORMELLEMENT EXCLUES, DANS LA MESURE AUTORISEE PAR LA LOI APPLICABLE, Y COMPRIS NOTAMMENT TOUTE GARANTIE IMPLICITE RELATIVE A LA QUALITE MARCHANDE, A L'APTITUDE A UNE UTILISATION PARTICULIERE OU A L'ABSENCE DE CONTREFAÇON.

Table of Contents

Preface
How This Book is OrganizedPreface-1
Using UNIX Commands
Accessing Sun Documentation OnlinePreface-2
Accessible Sun Configuration and Service Tracker Documentation Preface-2
Sun Welcomes Your CommentsPreface-3
Product Description
Introduction
Sun Configuration and Service Tracker Features
Tracking and Recording Events
Tracking Configuration
Data Archive
Collecting Hardware FRU Information
Viewing Events and Configuration Information
Benefits of Sun Configuration and Service Tracker for System Administration1- 5
Sun Configuration and Service Tracker Architecture
Sun Configuration and Service Tracker Server
Sun Configuration and Service Tracker Agent

.Sun Configuration and Service Tracker Repository 1-9
Sun Configuration and Service Tracker UI Console
Application Tracking Modules 1-12
Supported Systems 1-12
Sun Configuration and Service Tracker on Multi-Domain Systems 1-13
Sun Configuration and Service Tracker on Sun Enterprise 10000 1-13
Sun Configuration and Service Tracker on Sun Fire Platforms 1-14
Sun Fire 15K and 12K 1-14
Sun Fire 3800, 4800, 4810, 6800 1-14
Sun Configuration and Service Tracker on Clusters
Cluster Platform Hierarchy 1-17
Sun Configuration and Service Tracker on Volume Manager Systems 1-18
Tracking Sun JavaTM System Software Applications 1-20
Custom Event Application Programming Interface (API) 1-21
Data Feed to Sun
SRS Net Connect 1-24
Secure email
Installing Sun Configuration and Service Tracker
Introduction 2-2
Installation Package Disk Space Requirements 2-2
Supported Install Ontions 2-3
Operating System Ungrades 2-4
Sun Configuration and Service Tracker Server Installation 2-4
Sun Configuration and Service Tracker Server Requirements 2-4
Preparation for Sun Configuration and Service Tracker Server Installation 2-5
First Time Installation of Sun Configuration and Service Tracker Server 2-6

To Initially Install the Sun Configuration and Service Tracker Server2	-7
Upgrade of Sun Configuration and Service Tracker Server 2-	11
To upgrade a Sun Configuration and Service Tracker server 2-	11
Sun Configuration and Service Tracker Agent Installation 2-	14
Initial Installation of the Sun Configuration and Service Tracker Agent 2-	14
To Install the Sun Configuration and Service Tracker Agent 2-	15
Upgrade of the Sun Configuration and Service Tracker Agent 2-	18
To Upgrade the Sun Configuration and Service Tracker Agent 2-	18
Reinstallation of the Sun Configuration and Service Tracker Agent After (Upgrade	OS 20
To Install Sun Configuration and Service Tracker Agent Component on a Multi-domain Server	21
To Install the Sun Configuration and Service Tracker Agent on a Mult domain Server	ti- 21
Installation of Sun Configuration and Service Tracker on a SunTM Cluste 22	r2-
Sun Configuration and Service Tracker Agent Attachment 2-2	22
Attach an Agent to the Sun Configuration and Service Tracker Server. 2-2	22
To attach the agent to the Sun Configuration and Service Tracker service 2-23	er
To Attach a Multi-domain Agent to Sun Configuration and Service Tracked Server	er 23
cstattach on the Domains 2-2	24
Example 1 24	
Example 2 24	
cstattach on Sun Fire [™] 15K System Controller	24
Example 25	
To attach global platform data 2-2	25
cstattach on an E10K System Service Processor (SSP) 2-2	25

Example 26

To attach the global platform data 2-26
Agent Installation Verification 2-26
Unattached Agent Verification 2-27
To Verify an Unattached Agent
Attached Agent Verification 2-27
To Verify an Attached Agent 2-27
Decommissioning Sun Configuration and Service Tracker 2-28
Sun Configuration and Service Tracker Software Uninstall 2-28
To Uninstall Sun Configuration and Service Tracker Software 2-28
Sun Configuration and Service Tracker Features and Functions 3-1
Starting the Sun Configuration and Service Tracker UI Console 3-2
To Start the Sun Configuration and Service Tracker UI Console 3-2
Console Views
System Summary Section
Site Information
Site Info Dialog
To Enter Site Information 3-9
Global Cause Code Assignment 3-15
To Globally Assign a Cause Code
Custom Info
System Selection
To Select a System
Define Custom Fields
To Define a Custom Field 3-21
Record Custom Information 3-22

To Record Custom Information	3-23
Enterprise Hierarchy Section.	3-24
Sun Configuration and Service Tracker History Tab	3-24
To View Different Events	3-26
To Assign an Event Cause Code	3-27
To Add Comments to an Event	3-29
To Create a Service Event	3-29
To Look Up Configuration Changes	3-30
Configurations Tab	3-32
Applications Tab	3-35
To View Application Information	3-35
Statistics Tab	3-37
System Statistics	3-38
Application Statistics	3-40
Notification Tab	3-41
To Add a New Email to Event-list Mapping	3-43
To Delete an Email from Event-list Mapping	3-44
To Modify an Email-to-Event-list Mapping	3-44
Print Tab	3-46
To Specify a History Report	3-47
To Specify a Configuration Report	3-49
To Print or Email a Report	3-49
Logging Out	3-50
To Log Out	3-50
Sun Configuration and Service Tracker Administration	. 4-1
Authentication	. 4-1

User and Group Management 4-2
Sun Configuration and Service Tracker Access Control List (ACL) 4-2
To Create a cstadm or cstops Group 4-2
To Add a User to a cstadm or cstops Group 4-3
Sun Configuration and Service Tracker Access Levels 4-4
Site Registration
Prepare for Registration 4-6
Registration Prerequisites
To Obtain a Registration Key 4-8
Registration Completion 4-8
Network Protocols
To Set Network Transport Between Agent and Server
To Override the Random Port Assignment
To Force the Sun Configuration and Service Tracker Agent to Use TCP 4-10
To Set Network Transport Between Server and Client 4-11
Tuning Sun Configuration and Service Tracker Trigger Intervals 4-11
Tune Sun Configuration and Service Tracker Event Detectors 4-12
Sun Configuration and Service Tracker Detach 4-14
To Detach Sun Configuration and Service Tracker from Middleware Server
Sun Configuration and Service Tracker Tracking During OS Upgrades 4-15
To Restore A Copy of Sun Configuration and Service Tracker 4-15
Managing Hierarchy 4-16
Move Agent Data to a Different Hierarchy 4-16
To Alter the Hierarchy for an Agent
Service and Cause Code Updates 4-19

Sun Configuration and Service Tracker Utilities 5	-1
cstattach	-2
Name	-2
Description	-2
Supported Platforms 5	-2
Checklist 5	-3
Usage 5	-3
Examples 5	-4
Example 1 5	-4
Example 2 5	-5
Example 3 5	-5
Example 4 5	-5
cstattagt 5	-6
Name	-6
Description	-6
Supported Platforms 5	-7
Checklist	-7
Usage 5	-7
Example 1 5	-8
Example 2 5	-8
cstfind	-8
Name	-8
Synopsis	-8
Description	-9
Options	-9
Examples 5-	10
Example 1 5-	10

Example 2 5-11
Example 3 5-11
Example 4 5-11
Exit Status 5-11
findevent
Name
Description
Supported Platforms 5-13
Usage 5-13
EVENT_TYPE (Default is "any") 5-13
PERIOD
WEEKDAY 5-14
TIMESTART and TIMEEND 5-15
FORMAT
HIERARCHY 5-15
RULEFILE
Option 5-16
Usage Examples 5-16
cstlshost
Name
Synopsis
Description
Options
-f field name
-i inputfile
-o outputfile
Examples 5-19

Example 1	5-19
Example 2	5-20
Example 3	5-20
Exit Status	5-21
setcause	5-21
Name	5-21
Synopsis	5-21
Supported Sun Configuration and Service Tracker Releases	5-21
Features	5-22
Usage 1	5-22
Usage 2	5-22
PERIOD	5-22
RULEFILE	5-23
Set Cause Code Procedure (Usage 1)	5-24
Set Cause Code Procedure (Usage 2)	5-24
app_event	5-25
Name	5-25
Synopsis	5-25
Availability	5-25
Description	5-25
Operands	5-26
event-type	5-26
comment	5-26
Exit Status	5-27
Examples	5-27
Files	5-28
addsunfire	5-29

Name	29
Description	29
Supported Sun Fire Platforms	29
Inputs	30
Format	31
Usage Examples	32
Example 1 5-3	32
Exit Status	32
cstdecomm	32
Name	32
Synopsis	33
Description	33
Parameters	34
-t mm/dd/yyyy hh:mm:ss	34
-h hierarchy 5-3	34
Supported Platforms 5-3	34
Examples	34
Nodes with Hierarchy 5-3	35
Example 1 35	
Example2 35	
Nodes with no Hierarchy 5-3	35
Example 2 35	
Notes	35
Multi-domain/Node Systems	35
Examples of Usage 5-3	36
Troubleshooting Sun Configuration and Service Tracker	-1

Error Messages
Error, cannot set up TCP connection
Wrong Component (Agent vs Server) Selected During Install 6-2
Sun Configuration and Service Tracker Package Install Fails - Repository is a Sub-folder in /var/opt/SUNWcst
Error in Compiling Statistics
Site Registration Fails With Customer ID and Key
Cannot View FRUI Data on SF15K SC
Missing FRU Data for Mid-frame Sun Fire System Controllers 6-4
Sun Configuration and Service Tracker Platform Data Missing on Sun Fire 15K Main SC
Sun Configuration and Service Tracker Interface Reference
Sun Configuration and Service Tracker Console Functionality Descriptions 7-1
Event Cause Code Hierarchy 7-8
Index Index-1

Revision History

Revision	Date	Comments
1.0	10/25/2004	1st release: Sun Configuration and Service Tracker 3.5.2 revised for 3.5.1, 3.5.2 & Sun Control Station
1.1	06/30/2006	• GA release: Sun Configuration and Service Tracker 3.6.0 released.
1.2	08/10/2006	• Post 3.6.0 GA Release - Fixed issues related to images
		•
		•

Preface

This installation and operations guide describes the purpose, installation, features, functionality, and utilities of the Sun Configuration and Service Tracker software application, version 3.6.0

How This Book is Organized

This book contains the following information:

- Chapter 1, Product Description- provides an overall description of Sun Configuration and Service Tracker
- Chapter 2, Installing Sun Configuration and Service Tracker- describes how to install and upgrade Sun Configuration and Service Tracker
- Chapter 3, Sun Configuration and Service Tracker Features and Functions describes the functions included in the Sun Configuration and Service Tracker application and the console GUI features
- Chapter 4, Sun Configuration and Service Tracker Administration describes the functionality included in Sun Configuration and Service Tracker for the system administrator, including creating users, groups, network transport, and more
- Chapter 5, Sun Configuration and Service Tracker Utilities describes the included utilities and their purposes
- Chapter 6, Troubleshooting Sun Configuration and Service Tracker provides troubleshooting suggestions
- Chapter 7, Sun Configuration and Service Tracker Interface Reference contains terms and button names found in the GUI
- Index

Using UNIX Commands

This document does not contain information on basic UNIX® commands and procedures such as shutting down the system, booting the system, and configuring devices.

See one or more of the following for this information:

- AnswerBook2TM online documentation for the SolarisTM Operating Environment (Solaris)
- Other software documentation that you received with your Sun Microsystems (Sun) system

Accessing Sun Documentation Online

View a broad selection of documentation for Sun systems at this location on the Web:

http://www.sun.com/products-n-solutions/hardware/docs

Access a complete set of Solaris documentation and many other titles at this Website:

http://docs.sun.com

Accessible Sun Configuration and Service Tracker Documentation

An accessible HTML version of this document is available at this Website:

http://docs.sun.com

Click the **HELP** button in the Sun Configuration and Service Tracker user interface to view this document online.

Sun Welcomes Your Comments

Sun is interested in improving its documentation and welcomes your comments and suggestions. You can submit your comments by going to:

http://www.sun.com/hwdocs/feedback

Please include the title and part number of your document with your feedback:

Sun Configuration and Service Tracker 3.6.0 Customer Installation and Operations Guide, part number 819-6838-10

Sun Welcomes Your Comments

Chapter 1

Product Description

This chapter provides an overview of the Sun Configuration and Service Tracker software for version Sun Configuration and Service Tracker 3.6.0. It includes the following sections:

- "Introduction" on page 1-2
- "Sun Configuration and Service Tracker Features" on page 1-3
- "Benefits of Sun Configuration and Service Tracker for System Administration" on page 1-5
- "Sun Configuration and Service Tracker Architecture" on page 1-6
- "Supported Systems" on page 1-12
- "Sun Configuration and Service Tracker on Multi-Domain Systems" on page 1-13
- "Sun Configuration and Service Tracker on Clusters" on page 1-15
- "Sun Configuration and Service Tracker on Volume Manager Systems" on page 1-18
- "Tracking Sun JavaTM System Software Applications" on page 1-20
- "Custom Event Application Programming Interface (API)" on page 1-21
- "Data Feed to Sun" on page 1-23

Introduction

Sun Configuration and Service Tracker 3.6.0 is now released as a stand-alone product so that customers can benefit from its usage without having to depend upon additional Sun software products. The Sun Configuration and Service Tracker Server and Agent are both available in stand-alone form on the Sun website.

Sun Configuration and Service Tracker plays an important role in the overall strategy of proactive system management at a customer site. The software executing on each monitored host provides a macroscopic view of system configuration changes caused by failures, upgrades, and/or service activities over an extended period.

Sun Configuration and Service Tracker 3.6.0 includes a configuration for sending data automatically back to Sun Microsystems. The data is used by Sun to track system availability and performance and to continually improve Sun products and services. Availability Management System (AMS) is a secure database where the captured availability data is stored in Sun Microsystems.

Key capabilities of Sun Configuration and Service Tracker:

- Detects and notifies system configuration changes, including hardware, software, patch and system parameter changes
- Detects, time stamps, and records system events such as shutdown, reboot, panic, software and hardware changes, and multi-user availability

Event measurement precision can help achieve five nines/six sigma level metrics

- Stores data in formatted text repository for easy export
- Automates secure data feed into Sun's Availability Management System (AMS)
- Offers menu-driven uptime statistics generation
- Maintains automated backup of data
- Uses a three-tier architecture
- Runs with a small footprint, low-system impact execution, and small disk space requirement

Sun Configuration and Service Tracker Features

The Sun Configuration and Service Tracker application tracks and records event and configuration data to be viewed and reported through the Sun Configuration and Service Tracker user interface (UI).

Tracking and Recording Events

Sun Configuration and Service Tracker automatically detects the following events for the system on which it runs:

- Boot and reboot
- System shutdown or hang
- System panic, subsystem panic
- System runlevel change
- Software packages—installation and removal
- Software patches—addition and removal
- Dynamic attachment and detachment of system hardware
- Operating environment upgrade
- Sun Configuration and Service Tracker package upgrade and removal
- Changes to user-entered custom information
- Environmental changes detected through system interfaces

On Sun multi-domain systems, Sun Configuration and Service Tracker also detects the following events:

- System configuration changes across domains
- Board power-on
- Domain additions and deletions
- Hardware changes across domains
- On clusters:
 - Cluster node failovers
 - Cluster resource group failovers
- On Sun JavaTM System software

- Application Up/Down events
- Application configuration changes

Tracking Configuration

When an event is detected, Sun Configuration and Service Tracker captures a snapshot of the current system configuration information and categorizes it into the following categories:

- System information—includes the system model, host ID, host name, serial number, IP address, OS installed, number of CPUs, total memory, and number of disks
- Installed hardware—system hardware and peripheral devices (excluding external network and communication devices)
- Software packages—Sun and third-party packages (only those that are installed as software packages by the pkgadd command)
- Software patches
- Pertinent information about the SolarisTM Operating System
- Cluster configuration
- Volume Manager configuration
- Sun Java System software

Sun Configuration and Service Tracker determines and records the changes in the configuration of the system by comparing the new snapshot with the previous snapshot.

Data Archive

The Sun Configuration and Service Tracker development team has tracked the general use of the Sun Configuration and Service Tracker tool in almost 25,000 systems for more than 5 years, and the best case scenario usage reaches a maximum of 10,000 events per year. The average is around 4,000 to 5,000 events.

With 10,000 events per year, it will take 10 years for a history file to reach 100,00, or 20 years for a history file that has an average of 5,000 events per year. Sun Configuration and Service Tracker recommends that customers use the Sun Configuration and Service Tracker provided utility, cst_archive.

Collecting Hardware FRU Information

In UltraSPARC® III platforms, Sun Configuration and Service Tracker collects more detailed hardware information about the Field Replaceable Units (FRUs) in the system. This hardware information is in addition to the data collected by the hardware probe common to all Sun systems. The additional FRU data is viewable as a sub-category in the Installed Hardware section of the Configurations folder. This is considered part of Hardware Information and changes in the FRUs do not generate separate events.

For the Sun Fire 3800, 4800, 4810, and 6800 systems, Sun Configuration and Service Tracker collects FRU information remotely from the Sun Configuration and Service Tracker middleware server host.

Viewing Events and Configuration Information

Data in the Sun Configuration and Service Tracker server is accessed and viewed from the Sun Configuration and Service Tracker user interface. From the UI, a system administrator can view the configuration report and configuration change log for any host system on the network where the host is running Sun Configuration and Service Tracker.

The Sun Configuration and Service Tracker UI is also used interactively to enter service comments and cause codes for each event.

Benefits of Sun Configuration and Service Tracker for System Administration

Sun Configuration and Service Tracker provides a number of benefits for system administration including:

- Comprehensive listing of the current configuration of the system
- Time stamps of the last reboot and the frequency of system reboots
- Accurate log of when a device was removed or added to the system
- Statistical report of the system uptime for specific periods
- Ability to annotate comments of each event for future reference
- Ability to log service events for future reference
- Quick overview of the state of the Sun systems in the hierarchy
- Ability to track events by the reasons for their occurrence
- Increased system availability through pro-active configuration management

Sun Configuration and Service Tracker Architecture

Sun Configuration and Service Tracker 3.6.0 has the following components:

Sun Configuration and Service Tracker Server

Sun Configuration and Service Tracker server runs on the designated server system. The server receives data from all the reporting agents and stores it in the repository. The terms Sun Configuration and Service Tracker server and Sun Configuration and Service Tracker middleware mean the same thing, and they are used interchangeably in this document.

Sun Configuration and Service Tracker Agent

Sun Configuration and Service Tracker agent is the Sun Configuration and Service Tracker daemon running on the system tracked by the Sun Configuration and Service Tracker agent (aka host), and it reports all collected information when attached to a Sun Configuration and Service Tracker server.

Sun Configuration and Service Tracker Repository

The information from the agents is stored in the Sun Configuration and Service Tracker repository. This is stored as a fixed format (ASCII) file in a file system on the Sun Configuration and Service Tracker server.

Sun Configuration and Service Tracker UI and Console

The Sun Configuration and Service Tracker console is a Java-based user interface that can invoked from any Internet browser.

The functionality of the user interface is similar to the Sun Configuration and Service Tracker applet in previous releases of Sun Configuration and Service Tracker. The user interface allows a user to view and manage the Sun Configuration and Service Tracker collected events.

Application Tracking Modules

The application tracking modules are shared object call-back routines invoked by the Sun Configuration and Service Tracker agent to track the UP/DOWN of applications. There is one tracking module for each application.





Sun Configuration and Service Tracker Server

The Sun Configuration and Service Tracker server is a multi-threaded daemon running on the designated server system. It manages agent data reported by the various "attached" Sun Configuration and Service Tracker agents and communicates with the UI to display the collected data.

The server maintains all the agent data in a system. This data is maintained in unique folders within the file system for easy lookup and maintenance.

The Sun Configuration and Service Tracker server communicates to the Sun Configuration and Service Tracker console.

The Sun Configuration and Service Tracker server has the agent functionality built-in, which collects and tracks the configuration changes occurring on the system. Therefore, installing the Sun Configuration and Service Tracker agent on the Sun Configuration and Service Tracker server system is not required; however, the agent can be installed on a non-Sun Configuration and Service Tracker server host.

When registered, the Sun Configuration and Service Tracker server also sends the complete agent information back to Sun either via the SRS Net Connect 3.2 secure pipe or via secure email if SRS Net Connect 3.2 is unavailable.

Sun Configuration and Service Tracker Agent

Sun Configuration and Service Tracker Agent is a daemon that runs on each of the systems being tracked. The daemon detects whenever a change occurs and creates an event according to the change.

Sun Configuration and Service Tracker Agent can be attached or unattached. An unattached agent is a self-monitoring unit that collects data but does not report the data to any Sun Configuration and Service Tracker server. The user interface is not available for unattached agents.

When either the cstattach or cstattagt Sun Configuration and Service Tracker utility is used to make the connection, the Sun Configuration and Service Tracker agent starts reporting to a Sun Configuration and Service Tracker server, and the Sun Configuration and Service Tracker GUI is updated with the agent information. From that point forward, the agent data can be viewed using the GUI. For details on the utilities, see "cstattach" on page 5-2 and "cstattagt" on page 5-6. When the Sun Configuration and Service Tracker agent is not attached, the following information is available:

• Event information and configuration changes in the History file:

/var/opt/SUNWcst/cst_history

• Current configuration in:

/var/opt/SUNWcst/probe.current

• Notification to the email aliases specified in the Preferences file

All information collected by the daemon is also sent to the Sun Configuration and Service Tracker server on the middleware system for automatic backup. If the server system or its software cannot be reached, the data is backed up and transmitted again when the connection is reestablished.

Note – It is recommended that you do not make any manual changes, and that Notification email is set via the Sun Configuration and Service Tracker GUI console after the agent is attached to any Sun Configuration and Service Tracker Server.

If the Sun Configuration and Service Tracker agent is attached to a Sun Configuration and Service Tracker server, all the information collected by the daemon is also sent to the Sun Configuration and Service Tracker server on the middleware system for automatic backup. If the server system or its software cannot be reached, the data is backed up and transmitted when the connection is reestablished.

The Sun Configuration and Service Tracker "heartbeat" process ensures that a Sun Configuration and Service Tracker daemon is running and ready to collect data at all times

Sun Configuration and Service Tracker Repository

The repository resides in the server system. It holds the data Sun Configuration and Service Tracker collects from the tracked systems. The Sun Configuration and Service Tracker data is kept in a hierarchical directory structure, where each directory represents a specific system. The key data files in each directory are outlined in TABLE 1-1.



Caution – Do not edit these files manually. They are maintained by the Sun Configuration and Service Tracker software. Any edits will corrupt the file and disable software functionality.

TABLE 1-1 Sun Configuration and Service Tracker Repository Data Files

File Name	File Type	Description
cst_history	ASCII	Holds the event history, configuration changes, and comments for each event.
probe.current	ASCII	Holds the current configuration information.
probe.inception	ASCII	Holds the configuration snapshot information at the time Sun Configuration and Service Tracker was installed for the first time.
system.info	ASCII	Holds system environment details.
location.info	ASCII	Holds information about the location of the host.
asset.info	ASCII	Holds asset details of the monitored host.
service.info	ASCII	Holds service contract related information.
user.info	ASCII	Holds custom information as specified by the user.
cst.pref	ASCII	Holds Preferences information.
cause_code	Binary encoded	Holds the event cause codes for each event.
selective-event	ASCII	Holds local notification settings.
fruconfig.current	ASCII	Holds the current FRU configuration information.
fruconfig.inception	ASCII	Holds the FRU configuration information from the inception of Sun Configuration and Service Tracker.
volconfig.current	ASCII	Holds the current Veritas Volume Manager configuration information.
volconfig.inception	ASCII	Holds the Veritas Volume Manager configuration information from the inception of Sun Configuration and Service Tracker.
sc30config.current	ASCII	Holds current Sun Cluster 3.0 configuration information.
sc3.1config.current	ASCII	Holds current Sun Cluster 3.1 configuration information.

The directories in the repository are created automatically by the server based on the hierarchy information provided during the install of the Sun Configuration and Service Tracker agent, or at the time the agent is attached.

Sun Configuration and Service Tracker UI Console

Sun Configuration and Service Tracker UI can be invoked from anywhere using a web browser. To open a Sun Configuration and Service Tracker UI console, type in the following URL:

http://<server-host>/cst.html

OR

http://<server-host>/cstj2.html

The Sun Configuration and Service Tracker console is a Java-based graphical user interface, which shows all the monitored agent hosts in a hierarchical order. All the attached agent hosts can be accessed by selecting the agent name in the Enterprise View.

The GUI is invoked on the default port 8080 using Apache web server. If some other application or web server is already using this port, a different port should be used to invoke Sun Configuration and Service Tracker GUI. The new port number can be chosen by the user and should be updated in the httpd.conf file for Apache web server.

In such case, the GUI should be invoked in the below shown manner:

http://<server-host>:<new-port>/cst.html

OR

http://<server-host>:<new-port>/cstj2.html

For more information on how to change the Apache port number please refer to the Apache web server documentation.

Application Tracking Modules

Sun Configuration and Service Tracker 3.6.0 has built-in support to track the availability of all the Sun Java System software applications that are part of Sun JavaTM System. The tracking is achieved through callback routines invoked by the Sun Configuration and Service Tracker agent at pre-specified intervals.

The tracking modules are shipped bundled as part of the Sun Configuration and Service Tracker agent package and are automatically invoked when the Sun Configuration and Service Tracker agent is installed. They have the capability to detect the presence and the UP/DOWN status of the applications they are designed to track. The events are registered through a Sun Configuration and Service Tracker interface called *cstappev* for logging and forwarding.

Supported Systems

Sun Configuration and Service Tracker 3.6.0 supports all current Sun 4d- and 4u-based server platforms, Sun4u desktops, including the Sun Enterprise[™] 10000, and Sun Fire[™] platforms, both mid-range and high-end models. Sun Configuration and Service Tracker 3.6.0 software supports Sun Cluster 3.0 and 3.1 environments.

Sun Configuration and Service Tracker 3.6.0 runs in Solaris 2.6, 7, 8, 9, and 10 operating systems.

Sun Configuration and Service Tracker 3.6.0 does not support Solaris versions 2.4 and 2.5.1. Sun Configuration and Service Tracker versions 1.5.1 and 2.1U1 - both AMS and non-AMS releases, run on Solaris 2.5.1 and can report into a Sun Configuration and Service Tracker 3.6.0 server.

To view Sun Configuration and Service Tracker data through an applet requires a browser, such as Netscape, that supports JDK 1.2 or later.

Sun Configuration and Service Tracker on Multi-Domain Systems

Sun Configuration and Service Tracker 3.6.0 can be installed on and can track events on all Solaris/Sparc platforms, including Sparc III versions. The following sections describe Sun Configuration and Service Tracker support for the multi-domain Sun platforms.

Sun Configuration and Service Tracker on Sun Enterprise 10000

Since Sun Enterprise 10000[™] servers can have multiple domains and a System Service Processor (SSP) to manage the platform, multiple copies of Sun Configuration and Service Tracker must be run on this platform. One instance is installed and run on each of the domains. Also, a separate Sun Configuration and Service Tracker agent must be installed on the SSP.

Note – It is important that the Sun Configuration and Service Tracker agent is installed on the SSP. It should be installed on the SSP before installing on the domains.

Sun Configuration and Service Tracker on the SSP tracks the following events:

- System configuration changes
- Board power-on
- Domain changes
 - Domain(s) added
 - Domain(s) deleted
 - Hardware changes across domains

Sun Configuration and Service Tracker on the domain tracks the following events on that domain:

- Domain up or down
- Hardware/software changes

Sun Configuration and Service Tracker on Sun Fire Platforms

Sun Configuration and Service Tracker 3.6.0 is designed to support all Sun Fire[™] platforms:

- High-end systems: Sun FireTM 15K, 12K
- Midrange systems: Sun Fire[™] 3800, 4800, 4810, 6800

Sun Fire 15K and 12K

Sun Configuration and Service Tracker can track platform information from the system controllers on a Sun Enterprise 15K system, also known as a Sun Fire 15K and 12K.

The Sun Configuration and Service Tracker agent must be installed on the system controllers, and it must run on each of the domains. If the system has a spare system controller, the Sun Configuration and Service Tracker agent must also be installed on the spare system controller.

Sun Configuration and Service Tracker 3.6.0 supports creation of service events and annotation of event comments for system controllers and domains, but it does not support creation of service events or updates at the platform level.

The Sun Configuration and Service Tracker 3.6.0 application on the system controllers tracks the following events:

- Domain changes
- System configuration changes
- Platform configuration changes
- Other Sun Configuration and Service Tracker events

Sun Fire 3800, 4800, 4810, 6800

Sun Configuration and Service Tracker can track platform information for all Sun Fire systems.
Note – Since the system controllers on the SunFire midrange x8x0 systems are not Solaris OSs, Sun Configuration and Service Tracker cannot be installed directly on these system controllers. Therefore, the monitoring agent for these system controllers has to be installed on the middleware as part of the DST server and manually configured to provide the platform tracking capability.

To facilitate manual configuration described in the preceding note, use the Sun Configuration and Service Tracker utility, addsunfire. This utility helps configure the remote monitoring agent. For details on this utility, see "addsunfire" on page 5-29.

The Sun Configuration and Service Tracker agent is run on the Sun Fire midrange domains just as it is on other server systems.

Sun Configuration and Service Tracker on Clusters

When installed on Sun[™] Cluster 3.0 or Sun[™] Cluster 3.1 Cluster nodes, Sun Configuration and Service Tracker 3.6.0 tracks and provides a continuos record of the cluster membership and configuration changes. The data is stored in the repository as a formatted file and is available for viewing from the Sun Configuration and Service Tracker console. The information is viewable through a tabbed panel in the Configurations section of the Sun Configuration and Service Tracker UI.

The information is further sub-categorized into the following:

- Summary Information
- Membership Status
- Resource Group Information
- Resource List
- Resource Information
- Transport Path
- Device Group Information
- Quorum Votes

Sun Configuration and Service Tracker also detects various cluster failover events and records them in the Sun Configuration and Service Tracker history file. The events are annotated with additional relevant details such as cluster ID, affected resource group/node, failover status. These are available for viewing through the events table and the events comments section in the CST History folder.

The tracked cluster events are listed in TABLE 1-2.

Event Tracked	Cluster Version
Cluster node joined	SC3.0/3.1
Cluster node left	SC3.0/3.1
Resource group online	SC3.0/3.1
Resource group offline	SC3.0/3.1
Resource group state change	SC3.1
Cluster membership change	SC3.1
Cluster failover	SC3.1
HA-Oracle server started	SC3.0/3.1
HA-Oracle server stopped	SC3.0/3.1
HA-Oracle listener started	SC3.0/3.1
HA-Oracle listener stopped	SC3.0/3.1
HA-Sybase adaptive server started	SC3.0/3.1
HA-Sybase adaptive server stopped	SC3.0/3.1
HA-Sybase backup sever started	SC3.0/3.1
HA-Sybase backup sever stopped	SC3.0/3.1

 TABLE 1-2
 Sun Cluster Events Tracked

Note – The resource group, Online and Offline Events, can be used as an indication of each failover depending on the resource group type, which can be either Failover or Scalable/Load balancing resource group. In Sun Cluster 3.1, the event named "Cluster failover" is additional and is provided to give more detail on the reason of each failover.

Cluster Selection Image: Selection Resource Information Resource Group Information Resource List by group Resource Information Resource Type Information Transport Path Device Group Quorum Votes Name Value Value luster Name newclus Value Uster Version 3.1.0,REV=2003.03.2.6.13.14 Uster Uster ID newclus_0x43ABE33C,3.1_sc31_49d Code ocal Nodeiname testclus1 code Information Clusternod - priv ocal Interconnectname clusterrod - priv cluster ID cluster code - priv ocal Resource Groups 2 clusternod - priv clusternod - priv otal Nodeid 1 clusternod - priv clusternod - priv clusternod - priv ocal Interconnectname 2 2 clusternod - priv clusternod - priv otal Nodeid 2 2 clusternod - priv clusternod - priv ocal Interconnectname 2 2 clusternod - priv clusternod - priv otal Nodeid 2 2 clusternod - priv clusternod - priv clusternod - pri	Cluster Selection Image: Summary Member Status Resource Croup Information Resource List by group Resource Information Resource Type Information Transport Path Device Group Quorum Votes Name newclus Quorum Votes Stuster Version 3.1.0,REV=2003.03.25.13.14 Quorum Votes Outser Version 21.0,SEV=2003.03.25.13.14 Quorum Votes Call Nodename test/lus1 Colster Version Local Nodeid 1 Colster Version Quorum Votes Call Information 1 Colster Version Quorum Votes Call Nodeid 2 Colsternode1-priv Colster Version Jocal Nodeid 2 Clusternode1-priv Colsternode1-priv Cotal Resource Groups 2 Clusternode1-priv Colsternode1-priv Cotal Resource Groups 2 Quorum Votes Quorum Votes Resource Group Names Ustrumestrates SUNW LogicalHostname, SUNW SharedAddress Resource Group Names Clusternode1-priv, clusternode2-priv Quorum Votes	Cluster Selection Image: Summary Member Status Resource Group Information Resource List by group Resource Information Resource Type Information Transport Path Device Group Quorum Votes Name Value Value Cluster Name newclus Cluster Value Cluster Version 3.10,REV=2003.03.25.13.14 Cluster/D Local Nodename testclus1 Local Addet Local Nodeid 1 Local Nodeid 2 Coluster Version 2 Cluster Version 2 Total Resource Groups 2 2 Cluster Version Total Resource Types 2 2 Cluster Version Resource Group Names Testname, netgroup Resource Group Names Resource Types Resource Group Names SUNW LogicalHostname, SUNW SharedAddress Cluster node1-priv Construct Group Types SUNW LogicalHostname, SUNW SharedAddress Cluster node2-priv	System Information Installed Hardware	Software Packages Software Patches	Solaris Internal Info	Volume Manager	Cluster
	Summary Member Status Resource Group Information Resource List by group Resource Information Resource Type Information Transport Path Device Group Quorum Votes Name Quorum Votes Duster Name Name Value Duster Version 3.1.0,REV=2003.03.25.13.14 Value Suster ID newclus, 0x43ABE33C, 3.1_sC3.1_40d Josel Nodename testclus1 Jocal Nodeid 1 Jocal Nodeid 2 Total Resource Groups 2 Total Resource Types 2 Resource Group Names testclus1 Resource Group Names Cluster node1-priv.clusternode2-priv Guard Mathematica Clusternode2-priv	Summary Member Status Resource Group Information Resource List by group Resource Type Information Resource Type Information Transport Path Device Group Quorum Votes Name Quorum Votes Quorum Votes Cluster Name newclus Quorum Votes Cluster Version 31.0,REV-2003.03.25.13.14 Quorum Votes Jouster JD newclus,0x43ABE33C,31_sc31_49d Quorum Votes Local Nodeil 1 Quorum Votes Jouster JD newclus,0x43ABE33C,31_sc31_49d Quorum Votes Local Nodeil 1 Quorum Votes Jocal Nodeid 1 Quorum Votes Jordal Resource Groups 2 Z Total Resource Groups 2 Z Vermber Names testclus1 testclus2 Z Resource Group Names SUNW LogicalHostname,SUNW.SharedAddress Quorum Votes Resource Types SUNW LogicalHostname,SUNW.SharedAddress Quorum Votes	Cluster Selection				
Resource List by group Resource Information Resource Type Information Transport Path Device Group Quorum Votes Name Value Value Lister Name newclus Resource List by group Call Comment Lister Varsion 3.1.0,REV>2003.02.513.14 Resource List by Comment Resource List by Comment Call Nodeiame newclus/ValueSBC3.0,1_sc31_49d Comment Comment Call Nodeid festourse cluster Order Cluster Comment Call Nodeid festourse cluster Comment Cluster Comment Call Nodeid festourse cluster Comment cluster Comment Call Nodeid festourse cluster Comment cluster Comment Call Resource Groups 2 cluster Comment cluster Comment Staf Resource Types 2 cluster Comment cluster Comment Source Types SUMV/LisctLus2 cluster Comment cluster Comment Source Types SUMV/LisctLustrande.Diver Conterned Dover Conterned Dover Conterned Dover Conterned Dover Conterned Dover Conterned Dover ConternedDover Conterned Dover Conterned Dover ConternedDover Conterned D	Resource List by group Resource Information Resource Type Information Transport Path Device Group Ourum Votes Name Value Name Value Itster Name newclus Outure Value Name Name Value Itster Name newclus Outure Value Name Outer Value Name Dister Varian Name Value Outer Value Name Value Dister Varian Name Value Outer Value Name Value Dister Varian Name Value Outer Varian Value Value Value	Resource List by group Resource Information Resource Type Information Device Group Outom Votes Name Outom Votes Dister Name newclus Dister Varia 31.0,REV=2003.03.25.13.14 Dister Varia 31.0,REV=2003.03.25.13.14 Dister Varia newclus/AABE33C,3.1_sc31_49d Dister Varia newclus/AABE33C,3.1_sc31_49d Dister Varia Clusternode1-priv Dister Varia Clusternode1-priv Dister Varia 2 Orall Nodeid 2 Orall Resource Groups 2 Oral Resource Types Esclus1.1esclus2 Resource Group Names SUNW LogicalHostname,SUNW.SharedAddress Resource Types SUNW LogicalHostname,SUNW.SharedAddress	Summary	Member Status		Resource	Group Information
Transport Path Device Group O Quorum Votes Name Value tuster Name newclus tuster Varsion 3.1.0,REV=2003.03.25.13.14 tuster Varsion 3.1.0,REV=2003.03.25.13.14 tuster Varsion 1.0,REV=2003.03.25.13.14 tuster Varsion 1.0,REV=2003.03.25.13.14 tuster Varsion testclus1 ocal Nodename testclus1 ocal Nodeid 1 ocal Inderonnectname clusternode1-priv otal Resource Groups 2 otal Resource Groups 2 ender Resource Group Names testclus1,testclus2 esource Group Names Testname,netgroup esource Types SUWWLGaterhostname,SUNW.SharedAddress	Transport Path Device Group Quorum Votes Name Name Value Cluster Name newclus Cluster Yrsion 3.10,REV=2003.03.25.13.14 Cluster ID newclus,0x43ABE33C,3.1_sc31_49d Cocal Nodename testcus1 Local Interconnectname clustermode1-priv Total Resource Types 2 Afeotare Rame testcus1 Resource Types 2 Resource Types 2 Resource Types SUHWL LogicalHostname,SUHW.SharedAddress netronnect Hostnames clustermode1-priv,clustermode2-priv	Transport Path O Boeice Group O Quorum Votes Name Value Cluster Name newclus Cluster Version 3.1.0,REV=2003.03.25.13.14 Cluster Version 3.1.0,REV=2003.03.25.13.14 Cluster ID newclus,Ox43ABE33C,3.1_sc31_49d Local Nodename testclus1 Local Nodeid 1 Local Infectorinetiname clustermode1-priv Total Resource Trypes 2 Yeenber Names testclus1,testclus2 Resource Group Names Testame,tegroup Resource Trypes SUNWV.LogicalHostname,SUNWV.SharedAddress InterconnetHostnames clustermode1-priv,clustermode2-priv	 Resource List by group 	Resource Information		Resource	Type Information
Name Value luster Name newclus luster Version 3.1.0,REV=2003.03.26.13.14 luster ID newclus,0x43ABE33C,3.1_sc31_49d ocal Nodename testclus1 ocal Nodename testclus1 ocal Nodeid 1 ocal Nodeid 1 ocal Inferonnectname clustermode1-priv otal Resource Groups 2 otal Resource Types 2 enbert Names testclus1,testclus2 esource Group Names Testname,netgroup esource Types GUMWX/SharedAddress tescurpted Instrame_do.met/stramet/strame_do.met/strame_do.me	Name Value Cluster Version newclus Cluster Version 3.1.0,REV=2003.03.25.13.14 Cluster ID newclus,0x43ABE33C,3.1_sc31_49d Cluster ID newclus,0x43ABE33C,3.1_sc31_49d Jocal Nodename testcus1 Jocal Nodeid 1 Jocal Nodeid 2 Cotal Resource Types 2 Cotal Resource Types 2 dember Names testclus1, testclus2 Resource Group Names SUNWL LogicalHostname, SUNW.SharedAddress retronnet Hostnames clustermode1-priv, clustermode2-priv	Name Value Cluster Version newclus Cluster Version 3.1.0,REV=2003.03.25.13.14 Cluster ID newclus,0x43ABE33C,3.1_sc31_49d Local Nodename test/Lus1 Local Nodeid 1 Local Inforconnectname clusterrinde1-priv Cotal Resource Groups 2 Total Resource Types 2 Wember Names testclus1, testclus2 Resource Group Names SUNW/LogicalHostname,SUNW.SharedAddress Resource Types GUNW LogicalHostname,SUNW.SharedAddress Interconnect Hostnames clusternode1-priv, clusternode2-priv	 Transport Path 	🔾 Device Group		🔾 Quorum Vi	otes
Juster Name newclus juster Version 3.1.0,REV=2003.03.26.13.14 juster Version newclus,0v43ABE33C,3.1_sc31_49d ocal Nodename testclus1 ocal Nodeid 1 ocal Nodeid 1 ocal Indeconnectname clusterrode1-priv ocal Indeconnectname 2 otal Resource Groups 2 otal Resource Types testclus1,testclus2 esource Group Names Testname,netgroup esource Types SUMWLGastmame,SUNW,SharedAddress	Cluster Name newclus Cluster Version 3.1.0,REV=2003,32.5.13.14 Cluster UD newclus,Ux43ABE33C,3.1_sC31_49d Local Nodename testclus1 Local Nodeid 1 Local Nodeid clusternonectname Cotal Resource Groups 2 Cotal Resource Types 2 Alember Names testclus1 Resource Group Names 2 Resource Group Names SUNWL LogicalInostname, SUNW.SharedAddress nterconnect Hostnames clusternode1-priv, clusternode2-priv	Cluster Name newclus Cluster Version 3.1.0,REV=2003.3.25.13.14 Cluster UD newclus,0x43ABE33C,3.1_sc31_49d Local Nodename testclus1 Local Nodeid 1 Local Nodeid 1 Local Nodeid 1 Cotal Resource Groups 2 Total Resource Types 2 Member Names testclus1 Resource Group Names Testname,Rufroup Resource Types SUNW LogicalHostname,SUNW.SharedAddress InterconnetHostnames clusternode1-priv,clusternode2-priv	Nam	e		V	alue
Juster Version 3.1.0,PE-2003.03.25.13.14 Juster ID newclus,0x43ABE33C,3.1_sc31_49d ocal Nodename testclus1 ocal Nodeiame testclus1 ocal Inderconnectname clusternod1-priv ocal Inderconnectname clusternod1-priv otal Resource Groups 2 otal Resource Types 2 ember Names testclus1,sterclus2 esource Types SUWVLStaredAddress esource Types SUWVLStaredAddress	31.0,RFV-2003.03.25.13.14 Cluster ID newclus,0x43ABE33C,3.1_sc31_49d Cocal Nodename testclus1 Local Nodeld 1 Local Interconnectname clusternode1-priv Cotal Resource Groups 2 Cotal Resource Types 2 Aerober Names testclus1,testclus2 Resource Group Names SUNW LogicalHostname,SUNW SharedAddress nterconnect Hostnames clusternode1-priv,clusternode2-priv	31.0,RE->2003.03.25.13.14 Cluster ID newclus,Qx43ABE33C,3.1_sc31_49d Local Nodename testclus1 Local Noderid 1 _ocal Interconnectname clusternode1-priv Total Resource Groups 2 Total Resource Groups 2 Wember Names testclus1_testclus2 Resource Group Names SUNW LogicalHostname, SUNW.SharedAddress Interconnect Hostnames clusternode1-priv, clusternode2-priv	luster Name		newclus	1.05.918.000	
Juster ID newtlsp.gkr33C,3.1_sc31_49d ocal Nodeame testclus1 ocal Nodeid 1 ocal Inderconnectname clusternode1-priv otal Nodes 2 otal Resource Groups 2 otal Resource Types 2 ember Names testclus1,testclus2 esource Types Testname,netgroup esource Types SUWV/SharedAddress esource Types SUWV/Lostname,BUNW/SharedAddress	Cluster ID newclus,0x43ABE33C,3.1_sc31_49d _ocal Nodename testclus1 _ocal Nodename fullerconnectname _ocal Nodes 1 _ocal Nodes 2 Total Nodes 2 Total Resource Groups 2 Total Resource Types 2 Resource Group Names testclus1.testclus2 Resource Group Names SUNWL LogicalHostname,SUNW.SharedAddress nterconnect Hostnames clusternode1-priv,clusternode2-priv	Cluster ID newclus,0x43AEE33C,3.1_sc31_49d Local Nodename testclus1 Local Nodename testclus1 Local Interconnectname clustermode1-priv Local Inderconnectname clustermode1-priv Total Nodes 2 Total Resource Groups 2 Total Resource Types 2 Resource Types 2 Resource Group Names testclus1,testclus2 Resource Types SUNWL LogicalHostname,SUNW.SharedAddress Interconnect Hostnames clustermode1-priv,clustermode2-priv	Juster Version		3.1.0,REV=2003.03.25.1	3.14	
testClus1 ocal Noderame testClus1 ocal Nodeid 1 ocal Inderconnectname clusternode1-priv otal Nodes 2 otal Resource Groups 2 otal Resource Types 2 ember Names testclus1_testclus2 esource Group Names SUMWLCBstrame,BUNW.SharedAddress esource Types Outproved Dettame,SUNW.SharedAddress	Local Nodename testculs1 Local Nodeid 1 Local Interconnectname clustermode1-priv Total Nodes 2 Total Resource Types 2 dember Names testclus1_testclus2 Resource Group Names VINWL LogicalHostname,SUNW.SharedAddress reterconnect Hostnames clustermode1-priv,clustermode2-priv	Local Nodemame testuload Local Nodemame 1 Local Interconnectname clusternode1-priv Total Resource Groups 2 Total Resource Types 2 Member Names testulus1,testulus2 Resource Group Names Testame_netgroup Resource Types SUNW/LogicalHostname,SUNW.SharedAddress Interconnect Hostnames clusternode1-priv,clusternode2-priv	luster ID		newclus,0x43ABE33C,3.	1_sc31_49d	
ocal Nodeid 1 ocal Interconnectname clusternode1-priv ocal Interconnectname clusternode1-priv otal Nodes 2 otal Resource Groups 2 otal Resource Types 2 ember Names testLus1,testLus2 esource Group Names Testname,netgroup esource Types SUMWLCgicalHostname,SUNW.SharedAddress	ocal Interconnecthame 1 ocal Interconnecthame clustemode1-priv _ocal Interconnecthame 2 Total Resource Groups 2 Total Resource Types 2 Aember Names testclus1,testclus2 Resource Types SUNW LogicalHostname,SUNW.SharedAddress neter Types clustermode1-priv,clustermode2-priv	Local Noderd 1 Local Interconnethame clusternode1-priv Total Nodes 2 Total Resource Groups 2 Member Names testclus1_testclus2 Resource Group Names SUNW LogicalHostname,SUNW.SharedAddress Interconnet Hostnames clusternode1-priv,clusternode2-priv	ocal Nodename		testclus1		
ocal Interconnectname clustemode1-priv ocal Interconnectname clustemode1-priv otal Resource Groups 2 otal Resource Types 2 ember Names testclus1,testclus2 esource Types Testname,netgroup esource Types SUWVLCapicalHostname,SUNVXSharedAddress tercenced Hostname eluctomode1.priv	_ocal interconnectmame clustermode1-priv Total Nodes 2 Total Nodes 2 Total Resource Groups 2 Total Resource Types 2 dember Names testclus1,testclus2 Resource Group Names Testhame,netgroup Resource Types SUNW LogicalHostname,SUNW SharedAddress nterconnect Hostnames clustermode1-priv,clustermode2-priv	Local Interconnectname clusternode1-priv Total Nodes 2 Total Nodes 2 Total Resource Groups 2 Total Resource Types 2 Member Names testclus1.testclus2 Resource Group Names Testname,netgroup Resource Types SUNWL LogicalHostname,SUNW.SharedAddress interconnect Hostnames clusternode1-priv,clusternode2-priv	ocal Nodeld		1		
total Nodes 2 total Resource Groups 2 total Resource Types 2 ember Names testclus1,testclus2 esource Group Names Testname,netgroup esource Types SUWM/LigicalHostmame,SUNW/SharedAddress tescence Types SUMM/LigicalHostmame,SUNW/SharedAddress	lotal Nodes 2 Total Resource Groups 2 Total Resource Types 2 dember Names testclus1,testclus2 Resource Group Names Testname,netgroup Resource Types SUNW LogicalHostname,SUNW.SharedAddress nterconnect Hostnames clustermode1-priv,clustermode2-priv	Iotal Nodes 2 Total Resource Groups 2 Total Resource Types 2 Member Names testclus1jestclus2 Resource Group Names Vestname,netgroup Resource Types SUNWY LogicalHostname,SUNWS.sharedAddress nterconnect Hostnames clusternode1-priv.clusternode2-priv	.ocal Interconnectname		clusternode1-priv		
oral resource vroups 2 otal Resource Types 2 ember Names testclus1,testclus2 esource Group Names Testname,netgroup esource Types SUWVLSharedAddress tescopend Hectagene eluctomodel.pric (cutormode).pric	Lotal resource Groups 2 Total Resource Types 2 Wember Names testclus1,testclus2 Versource Group Names Testname,netgroup Sesource Types SUNWY LogicalHostname,SUNW/SharedAddress nterconnect Hostnames clusternode1-priv,clusternode2-priv	Lotal resource Groups 2 Total Resource Types 2 Wember Names testclus1,testclus2 Resource Group Names Testmane,Butyroup Resource Types SUNW LogicalHostname,SUNW;SharedAddress Interconnect Hostnames clusternode1-priv,clusternode2-priv	otal Nodes		2		
orai resource i ypes 2 orai resource i ypes 2 ember Names testlus1,testclus2 esource Group Names Testname,netgroup esource Types SUWM/LogicalHostname,SUNM/SharedAddress tercenzed Lectranze eluctorrodel.priz/ clustorrodel.priz/	India resource Types 2 Member Names testclus1,testclus2 Resource Types SUNW LogicalHostname,SUNW SharedAddress nterconnect Hostnames clusternode1-priv,clusternode2-priv	lotai resource rypes 2 Member Names testclus1,testclus2 Resource Group Names SUNWY LogicalHostname,SUNWY.SharedAddress Resource Types SUNWY LogicalHostname,SUNWY.SharedAddress Interconnect Hostnames clusternode1-priv,clusternode2-priv	otal Resource Groups		2		
eniber warres testilus j testilus j testilus z esource Group Names Testamen, BUNW. Shared Address esource Types SUNW. Logical Hostname, SUNW. Shared Address uncompact Hostname, SUNW. Shared Address	Resource Group Names Testinare, peticidary Jesticidary Jesticidary Jesticidary Jesticidary Jesticidary Jesticidary Jesticidary Antonio SUNW. Shared Address Source Types SUNW Logical Hostnames, SUNW. Shared Address clusternode 1-priv, clusternode 2-priv	Resource Trop Names Testname, netgroup Resource Trops Resource Tro	otal resource Types		Z		
esource Types SUNW.SharedAddress	resource Yndy Hanies resource Yndy Resource Yndy Resource Types SUNW LogicalHostname,SUNW SharedAddress nterconnect Hostnames clustermode1-priv,clustermode2-priv	resource Yrupp realies Internation (SUNW LogicalHostname,SUNW SharedAddress SUNW LogicalHostnames (Sunw LogicalHostname,SUNW SharedAddress clusternode1-priv,clusternode2-priv	remper marries		Tectnome notarour		
course types SOLVEY, Lugicial russ cluster and a 2014 to 2014	vesourise injues Soliviv.Euglicalmosinalities, Soliviv.Solaieuwuuless Interconnect Hostnames clusternode1-priv, clusternode2-priv	interconnect Hostnames clusternode1-priv,clusternode2-priv	esource ordup Names		el INW Logical Hactnam	o CLINIX/ Chorod&ddr	100
		Interventives roomantuu	terronnert Hostnames		clusternode1_nriv cluster	mode2-nriv	200
terconnect nosuralnes			nerconnect nostrannes		chusternouer-priv,cluster	nouez-piił	

FIGURE 1-2 Sun Configuration and Service Tracker on Sun Cluster

Cluster Platform Hierarchy

The CLUSTER_PLATFORM hierarchy is created on the server, and it is viewable from the Sun Configuration and Service Tracker UI. This feature enables users to view the following lists:

• The list of all clusters in the enterprise

Each cluster has a hierarchy inside CLUSTER_PLATFORM. The Sun Configuration and Service Tracker cluster ID hierarchy is created for each cluster, and the hierarchy name is in the following format:

<CLUSTER_NAME>,<CLUSTER_ID>,<CLUSTER_VERSION>

 The list of nodes inside each Sun Configuration and Service Tracker Cluster ID hierarchy A soft link for each node is created under the hierarchy for easy viewing of the cluster member. Clicking the node name displays generic cluster-node information.

Note – In the Sun Configuration and Service Tracker Enterprise View, each cluster node appears inside the CLUSTER_PLATFORM hierarchy and the user-specified hierarchy, which is specified during the Sun Configuration and Service Tracker agent installation. Clicking the same node in either hierarchy yields the same effect.

The Sun Configuration and Service Tracker Cluster ID hierarchy is a link to the following information:

- Global view of events received from all cluster members where duplicated events across the nodes are filtered
- The "Last configuration snapshot" in the Configuration Cluster folder to indicate the most recent view of the cluster

Note – Events in the Global Sun Configuration and Service Tracker History under "CST Cluster ID" hierarchy are logged and sorted based on the time when the Sun Configuration and Service Tracker server receives each event and not on the event timestamp.

Note – The Summary section of the Cluster configuration of the "CST Cluster ID" hierarchy reports the name of the last node with a configuration change.

Sun Configuration and Service Tracker on Volume Manager Systems

Volume Manager is viewable on a tabbed pane in the Configurations section of the Sun Configuration and Service Tracker UI.

CST History Co	onfigurations Ap	plications	Statistics	cs Notification		Prin	t	
Configuration Select Ourrent O Inc	ction eption						Edit Custom	Info
Software Patches	Solaris Internal I	Info Volume Manager Clu		Cluster	Custo	m info		
System Info	ormation	Insta	alled Hardware	a 👘	S	oftware	Packages	
Volume Manager S	election Disk Group 🔿 Ve	olumes 💿	Plexes 🔾 S	Sub Disks				
Name	Assoc		Length	KS	tate	1	State	
tpcvol001-01	tpcvol001	207392	20.	ENABLED	AC		IVE	-
tpcvo1001-02	tpcvol001	LOGON	1LY	ENABLED		ACT	IVE	
tpcvol002-01	tpcvol002	207392	20	ENABLED		ACT	IVE	
tpcvol002-02	tpcvol002	LOGON	1LY	ENABLED		ACT	IVE	
tpcvo1003-01	tpcvol003	207392	20	ENABLED		ACT	IVE	
tpcvo1003-02	tpcvol003	LOGON	1LY	ENABLED		ACT	IVE	-11
tpcvo1004-01	tpcvol004	207392	20	ENABLED		ACT	IVE	
tpcvol004-02	tpcvol004	LOGON	1LY	ENABLED		ACT	IVE	
tpcvo1005-01	tpcvol005	207392	20.	ENABLED		ACT	IVE	
tpcvol005-02	tpcvol005	LOGON	1LY	ENABLED		ACT	IVE	-11
tpcvo1006-01	tpcvol006	207392	20	ENABLED		ACT	IVE	
tpcvol006-02	tpcvol006	LOGON	ILY	ENABLED		ACT	IVE	
tpcvo1007-01	tpcvol007	207392	20	ENABLED		ACT	IVE	
tpcvol007-02	tpcvol007	LOGON	ILY .	ENABLED		ACT	IVE	-11
tpcvol008-01	tpcvol008	207392	20	ENABLED		ACTIVE		
tpcvol008-02	tpcvol008	LOGON	1LY	ENABLED		ACTIVE		
tpcvol009-01	tpcvol009	207392	20	ENABLED		ACT	ACTIVE	
tpcvol009-02	tpcvol009	LOGON	1LY	ENABLED		ACT	ACTIVE	
tpcvol010-01	tpcvol010.	207392	20.	ENABLED		ACT	IVE	
tpcvol010-02	tpcvol010	LOGON	1LY	ENABLED		ACT	IVE	-1
tpcvol011-01	tpcvol011	207392	20	ENABLED		ACT	IVE	
tneval011.02	tacvol011	1.000	II.V.	ENADIED		ACT	n/⊑	-

FIGURE 1-3 Volume Manager Configuration.

The information is further sub-categorized into the following groups:

- Disk Media
- Disk groups
- Volumes
- Plexes
- Sub Disks

Note – Volume Manager events and differences are included in the History folder.

Sun Configuration and Service Tracker tracks the standard events as listed in "Tracking and Recording Events" on page 1-3.

Tracking Sun Java™ System Software Applications

When installed on systems running one or more software applications of the Sun Java System, Sun Configuration and Service Tracker 3.6.0 has the built-in capability to track the availability and configuration changes of these applications. This tracking is achieved through custom tracking modules that are bundled with the Sun Configuration and Service Tracker 3.6.0 agent package.

TABLE 1-3 lists the Sun Java System software applications that are tracked:

Application Name	Version
Sun Java System Application Server	7
Sun Java System Calendar Server	6.0
Sun Java System Directory Server	5.2
Sun Java System Directory Proxy Server	5.2
Sun Java System Identity Server	6.1
Sun Java System Instant Messaging Server	6.0
Sun Java System Messaging Queue Server	3.0.1
Sun Java System Messaging Server	6.0
Sun Java System Portal Server	6.2
Sun Java System Web Server	6.1

 TABLE 1-3
 Sun Java System Software* Applications Tracked

*These applications were formerly known as Sun ONE applications.

There is a one-to-one mapping between the application and the tracking module. The tracking module has the capability to track multiple instances of the application running on the monitored host.

Each application and its specific instance are assigned a specific ID by the tracking module. The format for the ID is as follows:

<App Class>,<App Name>,<App Version>,<App Instance>

Example:

Sun Java System, Application Server, 7, domain1_admin-server

The tracking modules are loaded when the Sun Configuration and Service Tracker application is invoked on a monitored system. Subsequently, the tracking modules detect the presence of the application to be tracked, and determine the configuration and the instances in effect if found. The application and its instances are registered as "<Application> Registered" events through the cstappev interface. The modules then track the application on a continual basis, and register Application UP/DOWN events as well as events to notify configuration and usage snapshots.

All tracked information is stored both locally on the agent and on the central server to which the agent is attached. The collected data is available for viewing through the Sun Configuration and Service Tracker applet under the Applications tab. For more details, see "Applications Tab" on page 3-35.

Custom Event Application Programming Interface (API)

If there are applications on the system that are started or stopped through UNIX shell, awk, or perl scripts; the configuration changes, and start and stop activity on those applications can be monitored through Sun Configuration and Service Tracker. To manually register a custom event related to those applications, include the following line at the end of the application Start/Stop script:

/opt/SUNWcst/bin/app_event "event type" "comment"

The app_event relays the event only. It does not validate whether the application successfully started or stopped.

For example, the following line adds the machine password change as a Sun Configuration and Service Tracker event to the CST History log:

```
/opt/SUNWcst/bin/app_event "password changed" "By
machine owner"
```

Each time this line of code is included, Sun Configuration and Service Tracker registers the event in the CST History section of the Sun Configuration and Service Tracker UI. For more information, see "Sun Configuration and Service Tracker History Tab" on page 3-24.

To track such password changes automatically, add the following script to your crontab file, and run it at a convenient time and frequency, for example, every hour or every day.

```
#!/bin/sh
      # This script is used for creating a cst application event of
       # event type string "Password Change" by calling cst command
      # app_event. You need to add this script to your crontab file.
        # Get the CST packet name
        for i in SUNWcstu SUNWcst SUNWcstv SUNWcstve
        do
                pkginfo $i 2> /dev/null 1> /dev/null
                if test \$? = 0
                then
                        packname=$i
                        break
                fi
        done
# Get the installation base
        instbase='pkginfo -r $packname'
        # Set the full path to app_event
        app_event=$instbase"/"$packname"/bin/app_event"
```

```
# Get the time info of the file: /etc/passwd
        if test -f /tmp/cst_app_passwd
        then
                ls -l /etc/passwd | awk '{print $6, $7, $8}' >
/tmp/cst_app_passwd_new
               # Compare the time stamp of the passwd file, to see if
there is
                # any difference.
                diff /tmp/cst_app_passwd /tmp/cst_app_passwd_new >
/tmp/cst_result
                result=`ls -l /tmp/cst_result | awk '{print $5}'`
                if test $result != 0
                then
                        cp /tmp/cst_app_passwd_new /tmp/cst_app_passwd
                        # Call cst_app_event to register event
                     $app_event "Password Changed" "Changed by owner"
1> /dev/null
                fi
        else
                ls -l /etc/passwd | awk '{print $6, $7, $8}' >
/tmp/cst_app_passwd
        fi
        rm /tmp/cst_app_passwd_new
        rm /tmp/cst_result
        # End of the script
```

Data Feed to Sun

When the Data Feed to Sun is enabled, Sun Configuration and Service Tracker sends all tracked data to Sun in XML format through the secure SRS Net Connect 3.2 proxy.

SRS Net Connect

SRS Net Connect 3.2 is a self-managed system monitoring, configuration, patch and trend reporting tool. It is designed to enable Sun customers to monitor their Sun systems, and identify events before they can escalate into downtime. This tool is activated and used via the Web where customers view system status and configurations, trend and patch information, and alarms. Alarms can also be sent to the customer by email and pager.

The goal of SRS Net Connect 3.2 is to empower customers to proactively and preemptively manage their Sun server and storage systems in order to maximize system availability.

To send the data by SRS Net Connect 3.2 proxy, SRS Net Connect 3.2 must be installed on the Sun Configuration and Service Tracker server. If SRS Net Connect 3.2 is installed on the Sun Configuration and Service Tracker server when the Sun Configuration and Service Tracker server is already running, the Sun Configuration and Service Tracker server must be stopped with the following command. Type:

/opt/SUNWcstu/sbin/cstadm stop

After installing SRS Net Connect 3.2, restart the Sun Configuration and Service Tracker server using the following command:

#/opt/SUNWcstu/sbin/cstadm start

Note – Sun recommends installation and implementation of SRS Net Connect 3.2 because in addition to the encryption for the Sun Configuration and Service Tracker secure email, data transferred through the SRS Net Connect 3.2 transport is encrypted a second time using 128 bit encryption. Anyone attempting to break into and understand the data would have to break both the SSL security and the Sun Configuration and Service Tracker security.

Secure email

To send the data by secure email, the Sun Configuration and Service Tracker server must have sendmail installed.

The data is sent asynchronously—sent when a monitored host reports one or more of the following events:

- A new event
- A configuration change
- A cause code assigned to an event
- A comment provided for an event
- Changes made to system-specific custom information

The data content is usually less than 1KB in size except when large configuration changes are involved.

Periodically, Sun Configuration and Service Tracker sends summary information about the installed site to Sun. The summary data is used to checkpoint system status to provide accurate availability reporting.

If the continuous Data Feed to Sun is not enabled, a skeleton summary of the install base is still sent to a secure site within Sun once a week. This summary information is used to help generate statistics on Sun Configuration and Service Tracker deployment. For more details or to turn this ability on or off, contact your Sun representative.

Data Feed to Sun

Chapter 2

Installing Sun Configuration and Service Tracker

This chapter provides information on the following topics:

- "Introduction" on page 2-2
- "Sun Configuration and Service Tracker Server Installation" on page 2-4
- "Sun Configuration and Service Tracker Agent Installation" on page 2-14
- "Sun Configuration and Service Tracker Agent Attachment" on page 2-22
- "Agent Installation Verification" on page 2-26
- "Decommissioning Sun Configuration and Service Tracker" on page 2-28
- "Sun Configuration and Service Tracker Software Uninstall" on page 2-28

Introduction

Sun Configuration and Service Tracker 3.6.0 software has two components:

TABLE 2-	1 Sun	Configuration	and Service	Tracker Components	

Component	Description
Agent	Application installed on each Sun system to be tracked by Sun Configuration and Service Tracker.
Server (Middleware)	Application installed on the Sun system which acts as the server with the data repository and connects to Sun through the Sun Net Connect 3.2 proxy. It also includes the User console for server.

Sun Configuration and Service Tracker 3.6.0 has the SUNWcstv package, which is the server component. The server component can be downloaded from the Sun web site, and it should be installed on the server (middleware) machine.

Installation Package Disk Space Requirements

Install the Sun Configuration and Service Tracker 3.6.0 server packages on the selected server, and install the agent packages on each agent machine. The space requirements are described in TABLE 2-2:

Package Name	Installation Location	Disk Space Needed
SUNWcstv	Server	21.37 Mbytes
SUNWcstu	Agent	20.91 Mbytes

 TABLE 2-2
 Installation Package Disk Space Requirements

Supported Install Options

New install

An installation of Sun Configuration and Service Tracker on a Sun machine for the first time. Once any version of Sun Configuration and Service Tracker has been installed, installing another version is an upgrade and is not considered a new install.

Upgrade install

A version of Sun Configuration and Service Tracker has been installed, and can be upgraded to Sun Configuration and Service Tracker 3.6.0. Sun Configuration and Service Tracker 3.6.0 supports upgrading from the following Sun Configuration and Service Tracker versions:

- Sun Configuration and Service Tracker 1.5.1
- Sun Configuration and Service Tracker 1.5.1_AMS
- Sun Configuration and Service Tracker 2.1U1
- Sun Configuration and Service Tracker2.1U1_AMS
- Sun Configuration and Service Tracker1.5
- Sun Configuration and Service Tracker1.5_AMS
- Sun Configuration and Service Tracker2.1
- Sun Configuration and Service Tracker2.1_AMS
- Sun Configuration and Service Tracker 3.0
- Sun Configuration and Service Tracker 3.5
- Sun Configuration and Service Tracker 3.5.1
- Sun Configuration and Service Tracker 3.5.2

Sun Configuration and Service Tracker 3.6.0 does not support an upgrade from Sun Configuration and Service Tracker 1.0.1 or Sun Configuration and Service Tracker 1.1.3_AMS.

Reinstall after an Operating System upgrade

Sun Configuration and Service Tracker was previously installed on the machine, and all the data was removed from disk after an OS upgrade. You can reinstall Sun Configuration and Service Tracker so that it can detect an OS upgrade and restore all the original Sun Configuration and Service Tracker data back to the system.

Server install

Installation of the server component on a machine, which will serve as the Sun Configuration and Service Tracker middleware (server).

Agent install

Installation of the agent component on each host that is to be tracked for any configuration changes.

Operating System Upgrades

Ensure that a copy of Sun Configuration and Service Tracker is running on the systems at all times. Note that Sun Configuration and Service Tracker is not automatically installed as part of an OS upgrade. It must be added later.

Sun Configuration and Service Tracker Server Installation

This section contains the following topics:

- "Sun Configuration and Service Tracker Server Requirements" on page 2-4
- "Preparation for Sun Configuration and Service Tracker Server Installation" on page 2-5
- "First Time Installation of Sun Configuration and Service Tracker Server" on page 2-6
- "Upgrade of Sun Configuration and Service Tracker Server" on page 2-11



Caution – Do not install or upgrade the middleware and the agent software concurrently.

Sun Configuration and Service Tracker Server Requirements

Before the Sun Configuration and Service Tracker Server installation, the server must meet the following requirements:

• The server machine needs a central repository, which is a UFS (UNIX) file system, reserved to hold configuration and change history data for all other Sun Configuration and Service Tracker monitored nodes. The location of the repository should be provided at the time of installation.

Note – Please note that it is recommended that this location should exist before beginning the installation, else it will be created if the provided location is not found to be existing during the installation.

• The host that has been selected as the Sun Configuration and Service Tracker Server should have an Apache HTTP web server already installed.

This web server is required to view the GUI console. If it is not already installed, download and install it according to the Apache Installation manual.

• The UFS file system allocation should be 200 MBytes per year.

The space required to hold data for one node for one year is approximately two megabyte (2.0 MByte). Thus, for Sun Configuration and Service Tracker to track 100 nodes, the UFS file system allocation is approximately 200 MBytes per year.

• Either the SUNWfrusg package or the set of (optional) FRU ID packages must be installed on the Sun Configuration and Service Tracker middleware machine.

The installation of these packages enable Sun Configuration and Service Tracker to remotely track the FRU hardware information for SunFire system controllers. Contact your Sun representative for more details.

Since the FRU related libraries have a dependency on Solaris 8, or later, there is a constraint that a Sun Configuration and Service Tracker middleware machine should have Solaris 8, or later, installed. However, note that there is NO installation dependency between Sun Configuration and Service Tracker packages and the FRU related packages. The FRU packages can be installed at any time. Sun Configuration and Service Tracker starts using the libraries as soon as they are available.

Preparation for Sun Configuration and Service Tracker Server Installation

Note – If upgrading the agent and server, make sure the Sun Configuration and Service Tracker agent component installation has completed before initiating the server component install. If the server install starts while the Sun Configuration and Service Tracker agent is doing initialization or probe agent status, server installation is aborted, and errors are logged.

Have the following information available before you start to install SUNWcstv on the Sun Configuration and Service Tracker server machine.

• The path for the UFS file system served as Sun Configuration and Service Tracker repository database.

For more information, see "Sun Configuration and Service Tracker Server Requirements" on page 2-4.

• The path to the docs (or htdocs for Apache) directory of the http (Web) server.

This is the path where the index.html resides.

• The transport layer protocol to use between the agent and the server.

You can use TCP or UDP; by default, Sun Configuration and Service Tracker uses RPC over UDP.

Note – There is no cost for TCP protocol use between the agent and the server. The TCP protocol should be used sparingly and only on machines in the DMZ in the customer IT environment.

Proceed to one of the following sections:

- If you are installing SUNWcstv on a middleware server for the first time, go to "First Time Installation of Sun Configuration and Service Tracker Server" on page 2-6.
- If you are upgrading SUNWcstv on a middleware server where the Sun Configuration and Service Tracker server is already installed, go to "Upgrade of Sun Configuration and Service Tracker Server" on page 2-11.

First Time Installation of Sun Configuration and Service Tracker Server

The Sun Configuration and Service Tracker server software can be downloaded from the Sun website. It is available as a standalone package called SUNWcstv.

Note – While installing Sun Configuration and Service Tracker, remember that the Sun Configuration and Service Tracker software is only 'newly installed' the first time. A "new installation" of Sun Configuration and Service Tracker software means that no Sun Configuration and Service Tracker files or data exist on the agent system nor its server. If Sun Configuration and Service Tracker was running prior to an OS upgrade, the Sun Configuration and Service Tracker installation following the OS upgrade is treated as an upgrade not a new installation. Therefore, answer "No" when the installation script asks, "Is this the first time you have installed Sun Configuration and Service Tracker on this system?" This way, Sun Configuration and Service Tracker can extract the previous data from the server and detect the OS upgrade.

If you are performing an upgrade, proceed to "Upgrade of Sun Configuration and Service Tracker Server" on page 2-11.

To Initially Install the Sun Configuration and Service Tracker Server

As you install the software, the following installation log is displayed.

1. Download the Sun Configuration and Service Tracker server software from the Sun website and begin installation. Complete the following steps as the questions are displayed on your screen.

```
bash-2.05# pkgadd -d SUNWcstv.pkg
The following packages are available:
1 SUNWcstv Configuration and Service Tracker
        (sparc) 3.6.0
Select package(s) you wish to process (or 'all' to process
all packages). (default: all) [?,??,q]:
```

1. Press **<ENTER>** to accept the default.

```
Configuration and Service Tracker
(sparc) 3.6.0
Copyright 2004 Sun Microsystems, Inc. All rights reserved.
Use is subject to license terms.
The CST server stores all the agent data in a central
repository. This folder should be created by the site
administrator keeping in mind the space requirements for
this server.
If it is not already created, CST can create it now,
but make sure you have enough space on the UFS, where you
want it to be created.
Consult the CST documentation for more details.
Enter the CST Central Repository path :
```

 To indicate the Sun Configuration and Service Tracker Central Repository path, type: /export/cst

Note – You can choose your own path.

CST Repository created successfully and is set to /tmp/cst The webserver DOCUMENT ROOT path is the folder out of which the web-server(httpd) will serve the web documents. For example, on a system running the Apache web server, the usual document root path is /var/apache/htdocs. Consult the CST and the web-server documentation for details. Enter the HTTP ROOT path [/var/apache/htdocs] :

3. Press **ENTER** to accept the default.

Defaulting to "HTTPD_ROOT=/var/apache/htdocs"

```
## Executing checkinstall script.
Using </opt> as the package base directory.
## Processing package information.
## Processing system information.
## Verifying package dependencies.
## Verifying disk space requirements.
## Checking for conflicts with packages already installed.
## Checking for setuid/setgid programs.
This package contains scripts which will be executed with super-
user
permission during the process of installing this package.
Do you want to continue with the installation of <SUNWcstv> [y,n,?]
```

4. To continue with the installation, type: y

The software installs the packages of the Configuration and Service Tracker as <SUNWcstv>.

Note – This document does not list all the packages that are installed. This information is displayed on your monitor during the installation.

```
## Executing postinstall script.
Using existing cstops group
Using existing cstadm group
cstadm user not found. We are attempting to create a cstadm user.
This may take some time in an NIS environment while useradd
searches for the next available user id.
cstadm user added successfully.
```

As the installation continues, the software creates a cstadm user.

Note – This user can be used as the Sun Configuration and Service Tracker administrator.

```
Please make sure that /etc/group file contains entry similar to
this:
   % grep cstadm /etc/group
   cstadm::100:cstadm
```

5. Check the above mentioned file, and if the cstadm entry is not present against cstadm user, then manually edit the */etc/group* file and add the *cstadm* user to the cstadm group.

For example:

```
% grep cstadm /etc/group
```

cstadm::100:cstadm

Note – You must set the password for cstadm and use this password when you log in to the Sun Configuration and Service Tracker GUI.

The following information is displayed as the installation process completes:

```
CST is analyzing your system and generating a configuration
database.
This may take a while, please wait...
Analysis of system configuration is complete.
Registration record is not found.
CST: Send data to Sun = 0
Installation of <SUNWcstv> was successful.
```

After the Sun Configuration and Service Tracker Server is installed, the Sun Configuration and Service Tracker daemon, cstd.svr, and csthb.svr should be up and running. This indicates that the Sun Configuration and Service Tracker server package is installed, has initiated configuration tracking on this system, and has the directory structure set up to hold data for other hosts that will use this server as the middleware.

Upgrade of Sun Configuration and Service Tracker Server

Sun Configuration and Service Tracker 3.6.0 supports upgrades from all previously installed Sun Configuration and Service Tracker server versions. The upgrade is included in the SUNWcstv package itself, and much of the procedure is automated.



Caution - /Do not install or upgrade the middleware and the agent software concurrently.

Note – If Sun Configuration and Service Tracker was running prior to an OS upgrade, the Sun Configuration and Service Tracker installation following the OS upgrade is treated as an upgrade not a new installation. If you are preforming an upgrade, answer "No" when the installation script asks, "Is this the first time you have installed Sun Configuration and Service Tracker on this system?" Sun Configuration and Service Tracker can extract the previous data from the server and detect the OS upgrade.

To upgrade a Sun Configuration and Service Tracker server

- 1. Log in as the superuser.
- 2. To remove the existing Sun Configuration and Service Tracker server packages, type the following program command that is appropriate for your system:

```
# pkgrm SUNWcstve
or
# pkgrm SUNWcstv
or
# pkgrm SUNWcstu
```

3. Install the Sun Configuration and Service Tracker Server package, which includes the Sun Configuration and Service Tracker upgrade.

The upgrade script does not ask any questions because the initial installation of Sun Configuration and Service Tracker has already saved data in the /var/opt/SUNWcst directory. The script automatically installs the server component in that directory.

As you install the software, the following installation log is displayed.

```
The following packages are available:

1 SUNWcstv Configuration and Service Tracker

(sparc) 3.6.0

Select package(s) you wish to process (or 'all' to process

all packages). (default: all) [?,??,q]:
```

4. Press ENTER to accept the default.

```
## Executing checkinstall script.
Using </opt> as the package base directory.
## Processing package information.
## Processing system information.
## Verifying package dependencies.
## Verifying disk space requirements.
## Checking for conflicts with packages already installed.
## Checking for setuid/setgid programs.
This package contains scripts which will be executed with super-
user
permission during the process of installing this package.
Do you want to continue with the installation of <SUNWcstv>
[y,n,?]
```

5. To continue with the installation, type: \mathbf{y}

The software installs the packages of the Sun Configuration and Service Tracker as <SUNWcstv>.

Note – This document does not list all the packages that are installed. This information is displayed on your monitor during the installation.

As the installation continues, the software creates a cstadm user.

```
## Executing postinstall script.
Using existing cstops group
Using existing cstadm group
cstadm user not found. We are attempting to create a cstadm user.
This may take some time in an NIS environment while useradd
searches
for
the next available user id.
cstadm user added successfully.
Please make sure that /etc/group file contains entry similar to
this:
  % grep cstadm /etc/group
  cstadm::100:cstadm
```

6. Check the above mentioned file, and if the cstadm entry is not present against cstadm user, then manually edit the /etc/group file and add the cstadm user to the cstadm group:

```
% grep cstadm /etc/group 
cstadm::100:cstadm
```

Note – You must set the password for cstadm and use this password when you log in to the Sun Configuration and Service Tracker GUI.

The following information is displayed as the installation process completes.

```
Fresh-install/upgrade from non-AMS. Unregistered
CST: Send data to Sun = 0
Installation of <SUNWcstv> was successful.
```

Sun Configuration and Service Tracker Agent Installation

The Sun Configuration and Service Tracker agent is the application that resides on each Sun machine to be monitored by Sun Configuration and Service Tracker. The Sun Configuration and Service Tracker agent can be downloaded as package *SUNWcstu* and installed on a Sun system.



Caution – Do not install or upgrade the middleware and the agent software concurrently.

This section contains the following topics:

- "Initial Installation of the Sun Configuration and Service Tracker Agent" on page 2-14
- "Upgrade of the Sun Configuration and Service Tracker Agent" on page 2-18
- "Reinstallation of the Sun Configuration and Service Tracker Agent After OS Upgrade" on page 2-20
- "To Install Sun Configuration and Service Tracker Agent Component on a Multi-domain Server" on page 2-21
- "Installation of Sun Configuration and Service Tracker on a SunTM Cluster" on page 2-22

Initial Installation of the Sun Configuration and Service Tracker Agent

As you install the software, the following agent installation log is displayed. The following steps provide the required information you need to complete each part of the installation.

To Install the Sun Configuration and Service Tracker Agent

```
bash-2.05# pkgadd -d SUNWcstu.pkg
The following packages are available:
    1 SUNWcstu Configuration and Service Tracker
                (sparc) 3.6.0
Select package(s) you wish to process (or 'all' to process
all packages). (default: all) [?,??,q]:
```

1. Press Enter to accept the default to install all packages.

```
Processing package instance <SUNWcstu> from
</usr/local/SunSoftware/CST3.6.0/SUNWcstu.pkg>
Configuration and Service Tracker
(sparc) 3.6.0
Copyright 2004 Sun Microsystems, Inc. All rights reserved.
Use is subject to license terms.
No CST footprints were found on this system.
```

```
Note: If the CST data was deleted for any reason
  (an OS upgrade for example), this installation
      can try and restore the data if the (previous)
      server name for this agent is specified.
Do you want to try restoring CST data ? [n] [y,n,?,q]
```

2. Press Enter to accept the default of no.

Note – If you are reinstalling the Sun Configuration and Service Tracker Agent, type y to have the application try to restore the Sun Configuration and Service Tracker data.

```
CST Daemons can be started by this package install.
However, you can choose to prevent that from happening
at this time.
Do you want to start CST daemons ? [y] [y,n,?,q]
```

3. Press **Enter** to accept the default to start the Sun Configuration and Service Tracker daemons.

```
## Executing checkinstall script.
Using </opt> as the package base directory.
## Processing package information.
## Processing system information.
## Verifying package dependencies.
## Verifying disk space requirements.
## Checking for conflicts with packages already installed.
## Checking for setuid/setgid programs.
This package contains scripts which will be executed with super-
user permission during the process of installing this package.
Do you want to continue with the installation of <SUNWcstu>
[y,n,?]
```

To continue installing the Sun Configuration and Service Tracker Agent, type:

The software installs the packages of the Sun Configuration and Service Tracker as <SUNWcstu>.

Note – This document does not list all the packages that are installed. This information is displayed on your monitor during the installation.

As the installation finishes, you are directed to attach the Sun Configuration and Service Tracker Agent to the Sun Configuration and Service Tracker Server:

```
## Executing postinstall script.
CST Agent package is now installed.
Please use CST documentation to attach this CST agent
to a CST server.
Consult CST documentation for details about the attach procedure.
Installation of <SUNWcstu> was successful.
```

To attach the Sun Configuration and Service Tracker Agent to the Sun Configuration and Service Tracker Server, proceed to "Sun Configuration and Service Tracker Agent Attachment" on page 2-22.

Upgrade of the Sun Configuration and Service Tracker Agent

Sun Configuration and Service Tracker 3.6.0 supports upgrading the Sun Configuration and Service Tracker agent from all the previous Sun Configuration and Service Tracker versions except Sun Configuration and Service Tracker 1.0.1 and Sun Configuration and Service Tracker 1.1.3_AMS and for situations where the Sun Configuration and Service Tracker 3.6.0 agent is uninstalled and reinstalled.

To Upgrade the Sun Configuration and Service Tracker Agent

- 1. Log in as the superuser.
- 2. Remove the existing Sun Configuration and Service Tracker agent package, SUNWcst or SUNWcstu; run the pkgrm command for the file that is currently installed:

pkgrm SUNWcst

or

pkgrm SUNWcstu

As you install the software, the following agent installation log is displayed. The following steps provide the required information you need to complete each part of the installation.

```
bash-2.05# pkgadd -d SUNWcstu.pkg
The following packages are available:
    1 SUNWcstu Configuration and Service Tracker
        (sparc) 3.6.0.0
Select package(s) you wish to process (or 'all' to process
all packages). (default: all) [?,??,q]:
```

3. Press **Enter** to accept the default to install all packages.

```
Processing package instance <SUNWcstu> from
</usr/local/SunSoftware/CST3.6.0/SUNWcstu.pkg>
Configuration and Service Tracker
(sparc) 3.6.0
Copyright 2004 Sun Microsystems, Inc. All rights reserved.
Use is subject to license terms.
## Executing checkinstall script.
Using </opt> as the package base directory.
## Processing package information.
## Processing system information.
## Verifying package dependencies.
## Verifying disk space requirements.
## Checking for conflicts with packages already installed.
## Checking for setuid/setgid programs.
This package contains scripts which will be executed with super-
user
permission during the process of installing this package.
Do you want to continue with the installation of <SUNWcstu>
[y,n,?]
```

4. To continue with the installation of <SUNWcstu>, type y

The software installs the packages of the Sun Configuration and Service Tracker Agent as <SUNWcstu>.

Note – This document does not list all the packages that are installed. This information is displayed on your monitor during the installation.

When the installation finishes, you are informed that the installation was successful:

```
## Executing postinstall script.
```

Installation of <SUNWcstu> was successful.

Reinstallation of the Sun Configuration and Service Tracker Agent After OS Upgrade

Caution – If you upgrade your operating system on the Sun Configuration and Service Tracker server machine after you have installed and operated Sun Configuration and Service Tracker, the Sun Configuration and Service Tracker data stored on the server in the Sun Configuration and Service Tracker repository is lost unless you back up the data prior to the OS upgrade.

To re-install an agent after an OS upgrade, please follow the instructions in section, "Initial Installation of the Sun Configuration and Service Tracker Agent" on page 2-14.

Important! – When asked "Do you want to try restoring CST data ? [n] [y,n,?,q]" type y to indicate yes, and complete the instructions that are displayed on your monitor.

To Install Sun Configuration and Service Tracker Agent Component on a Multi-domain Server

Sun multi-domain servers include either a system service processor (SSP) or a system controller (SC). The installation of Sun Configuration and Service Tracker on a multi-domain server is the same on both types of platforms.

Sun Configuration and Service Tracker on the SSP or SC and Sun Configuration and Service Tracker on the domains collectively give the complete information regarding the multi-domain platform. It is required that you install Sun Configuration and Service Tracker first on the SSP or SC and then on the domains. Be aware that the Sun Configuration and Service Tracker agent installs in unattached mode by default, and the agent must be attached to a running Sun Configuration and Service Tracker middleware machine.

The Sun Configuration and Service Tracker attach functionality is designed to ensure a consistent hierarchical structure within the hierarchical view for the multi-domain server supported by its SSP or SC.

To Install the Sun Configuration and Service Tracker Agent on a Multi-domain Server

1. Install SUNWcstu on the SSP or SC.

It may take SUNWestu up to 30 minutes to probe the SSP or SC configuration. During this time, the Sun Configuration and Service Tracker SC software automatically detects the platform, and SSP names and creates the appropriate hierarchy.

- 2. Install SUNWcstu on all the existing domains.
- 3. Whenever a new domain is added, install SUNWcstu on that domain.

Installation of Sun Configuration and Service Tracker on a Sun™ Cluster

Installing Sun Configuration and Service Tracker on a Sun Cluster is essentially the same as installing Sun Configuration and Service Tracker on its individual nodes. The installation on various nodes can be done in any sequence. No specific setup is required. Sun Configuration and Service Tracker 3.6.0 can track events from Sun Cluster 3.0 and Sun Cluster 3.1.

Note – For easy manageability, ensure that during installation the various nodes of a cluster are grouped closely within a well defined hierarchy.

Proceed to "Sun Configuration and Service Tracker Server Installation" on page 2-4.

Sun Configuration and Service Tracker Agent Attachment

The following topics are included in this section:

- "Attach an Agent to the Sun Configuration and Service Tracker Server" on page 2-22
- "To Attach a Multi-domain Agent to Sun Configuration and Service Tracker Server" on page 2-23

Attach an Agent to the Sun Configuration and Service Tracker Server

When an agent is installed but has not been previously attached to a middleware system, you must bind the Sun Configuration and Service Tracker agent to the Sun Configuration and Service Tracker middleware system by running either the *cstattach* utility or the *cstattagt* utility.

By attaching an agent to Sun Configuration and Service Tracker middleware system, you can do the following:

• View the data of the attached agents collected in the repository of the Sun Configuration and Service Tracker server.

View the Sun Configuration and Service Tracker agent data through Sun Configuration and Service Tracker UI. The data includes system events, system configuration, and system availability data.

• Annotate an outage event cause code using the GUI or command line interface.

To attach the agent to the Sun Configuration and Service Tracker server

- 1. Complete one of the following steps:
 - Execute the *cstattach* utility from the Sun Configuration and Service Tracker server.
 - Execute the *cstattagt* utility from the host where the agent is running.
- 2. Specify the protocol to be used between the agent and the server as input arguments to the attach utilities: TCP or UDP.
 - The usage format for cstattach is:

```
cstattach [-h hierarchy] [-m middleware] [-t transport] -a
<agentname> -k <agentkey>
```

The *cstattach* utility must be run from the server.

• The usage format for cstattagt is:

cstattagt [-h hierarchy] [-t transport] <middleware>

The *cstattagt* utility must be run from the agent.

Note – For more information, see "cstattach" on page 5-2 or "cstattagt" on page 5-6 depending upon the utility you are using to attach the agent.

To Attach a Multi-domain Agent to Sun Configuration and Service Tracker Server

These guidelines apply to the following Sun system platforms.

■ Sun FireTM 15K domains and system controller

- Sun Enterprise 10000 (E10k) domains and SSP
- Other multi-domain systems, including Sun Fire 3800, 4800, 4810, and 6800 domains and system controllers

cstattach on the Domains

It is recommended that the domains be grouped together using the following hierarchy guideline. The hierarchy can be specified using the -h option when using the cstattach command.

```
[USER_DEFINED_HIERARCHY]/[PLATFORM_NAME]
```

USER_DEFINED_HIERARCHY is optional. When you use the hierarchy option, the Sun Fire system or E10K platform name should be added at the end of the hierarchy value.

Example 1

To attach an SF15K domain with the platform name, "clyde," type:

```
# cstattach -h department1/group2/clyde -a
sunfiredomain1.eng.sun.com -k 123456
```

Example 2

To attach the same node with no user defined hierarchy, type:

```
# cstattach -h clyde -a sunfiredomain1.eng.sun.com
-k 123456
```

cstattach on Sun Fire™ 15K System Controller

Sun Configuration and Service Tracker provides support for the following tracking on an SSC:

• SSC host tracking data (similar to domain systems).

The attach process can be accomplished using *cstattach*.

• Global platform tracking data.

The attach process is a manual procedure and is optional.
To attach an SSC system, the hierarchy should be in the following format:

[USER_DEFINED_HIERARCHY]/[PLATFORM_NAME]/SSC

This differs from the domain in that SSC (the fixed acronym) is added at the end of the platform hierarchy command.

Example

```
# cstattach -h clyde/SSC sunfiressc1.eng.sun.com
123456
```

To attach global platform data

- 1. Log into the main SSC system.
- 2. Change to the directory where platform data is stored; type:

```
cd /var/opt/SUNWcst/ssc
```

3. Create a compressed (tar) file of the data stored in that directory; type:

```
tar cvf /tmp/ssc.tar *
```

This creates a file named ssc.tar.

4. Transfer the tar file to the Sun Configuration and Service Tracker middleware system and extract the content to the path; type the following command:

[repository_path]/[USER_DEFINED_HIERARCHY]/[PLATFORM_ NAME]

5. Unlock the platform tracking functionality by writing a 0 to the file on the system controller; type: /var/opt/SUNWcst/ssc/comm_lock

cstattach on an E10K System Service Processor (SSP)

Sun Configuration and Service Tracker provides support for the following tracking on an E10K SSP:

• SSP host tracking data (similar to domain systems).

The attach process can be accomplished using the *cstattach* utility.

Global platform tracking data.

The attach process is a manual procedure and is optional.

To attach an SSP system, the hierarchy should be in the following format:

[USER_DEFINED_HIERARCHY]/[PLATFORM_NAME]/SSP

This differs from the domain in that SSP (the fixed acronym) is added at the end of the platform hierarchy command.

Example

The E10K platform in this example has the name, clyde.

```
# cstattach -h clyde/SSP e10kssp1.eng.sun.com 123456
```

To attach the global platform data

- 1. Log into the main SSP system.
- 2. Change to the directory where platform data is stored; type:

```
cd /var/opt/SUNWcst/ssp
```

3. Create a compressed (tar) file of the data stored in that directory; type:

tar cvf ssp.tar *

This creates a file named ssp.tar.

4. Transfer the tar file to the Sun Configuration and Service Tracker middleware system and extract the content to the path; type:

[repository_path]/[USER_DEFINED_HIERARCHY]/[PLATFORM_ NAME]

5. Unlock the platform tracking functionality by writing a 0 to the file on the E10K service system processor; type:

/var/opt/SUNWcst/ssp/comm_lock

Agent Installation Verification

There are two scenarios when you verify installation:

- To verify an unattached agent
- To verify an attached agent.

Unattached Agent Verification

If the cstd.agt and the csthb.agt processes are running the agent installation is complete. If not, there is something wrong with the agent installation. For more information, check the /var/opt/SUNWcst/cstlog directory.

To Verify an Unattached Agent

- At the prompt, type the following command: ps -aef | grep cst
- 2. Check that the following processes are running:
 - cstd.agt
 - csthb.agt.

Attached Agent Verification

If the MIDDLEWARE is assigned a host name, it is attached to that host (Sun Configuration and Service Tracker Server). If the cst.pref file is not present or there is no entry against the variable MIDDLEWARE, the agent is not attached.

To Verify an Attached Agent

- At the prompt, type the following command: ps -aef | grep cst
- 2. Check that the following processes are running:
 - cstd.agt
 - csthb.agt
- To check that the MIDDLEWARE is assigned a host name indicating it is attached, type the following command: cat /var/opt/SUNWcst/cst.pref

Decommissioning Sun Configuration and Service Tracker

When the tracking of events is to be stopped on a host, such that availability tracking and reporting for this host can be terminated on the Sun side, the *cstdecomm* utility must be executed.

Execution of this utility accomplishes the following:

- Appends a marker event called "Tracking Ended" to the history file
- Moves the data for this host to a separate DECOMMISSIONED_AGENTS directory
- Detaches the host from the middleware

For more details on this utility, see "cstdecomm" on page 5-32.

Sun Configuration and Service Tracker Software Uninstall

This section explains how to uninstall Sun Configuration and Service Tracker 3.6.0 software.



Caution – Do not remove the repository directory from the Sun Configuration and Service Tracker server that was created when Sun Configuration and Service Tracker was first installed. Sun Configuration and Service Tracker collected data will be lost if the repository directory is removed.

To Uninstall Sun Configuration and Service Tracker Software

- 1. Log in as a superuser.
- 2. Check that the Sun Configuration and Service Tracker package exists; type:
 - # pkginfo | grep cst

As you uninstall the software, the following uninstall log is displayed. The following steps provide the required information you need to complete each part of the uninstall to remove the Sun Configuration and Service Tracker installation from your hosts.

```
bash-2.05# pkgrm SUNWcstv
The following package is currently installed:
    SUNWcstv Configuration and Service Tracker
        (sparc) 3.6.0.0
Do you want to remove this package? [y,n,?,q]
```

3. To remove the package and uninstall Sun Configuration and Service Tracker software, type: **y**

```
## Removing installed package instance <SUNWcstv>
This package contains scripts which will be executed with
super-user permission during the process of removing this
package.
Do you want to continue with the removal of this package
[y,n,?,q]
```

4. To continue removing the package and all associated packages and scripts, type: y

Verifying package dependencies.
Processing package information.
Executing preremove script.
Using CATALINA_BASE: /var/cstadm
Using CATALINA_HOME: /var/cstadm/temp
Using JAVA_HOME: /usr/java
Removing pathnames in class <mw>
/opt/SUNWcstv/modules/cst_svrim.so

A list of package dependencies and pathnames are listed during the uninstall. When the following information is displayed, the uninstall is complete.

```
/opt/SUNWcstv
## Executing postremove script.
## Updating system information.
Removal of <SUNWcstv> was successful.
```

5. If you want to remove the Sun Configuration and Service Tracker software footprint left on the machine (required if you want to perform a new install of Sun Configuration and Service Tracker), type:

```
# rm -rf /var/opt/SUNWcst
```



Caution – On your server system, you must remove SUNWecsts first, then SUNWcstu. On an agent, remove SUNWecst first, then SUNWcstu.

Note – If you want to totally remove Sun Configuration and Service Tracker and want to perform a new install, you must remove the directory, /var/opt/SUNWcst, on the agent machine.

Chapter 3

Sun Configuration and Service Tracker Features and Functions

This chapter describes the various features and functions of the Sun Configuration and Service Tracker console. It includes the following sections:

- "Console Views" on page 3-4
- "System Summary Section" on page 3-5
- "Site Information" on page 3-7
- "Global Cause Code Assignment" on page 3-15
- "Custom Info" on page 3-18
- "Enterprise Hierarchy Section" on page 3-24
- "Sun Configuration and Service Tracker History Tab" on page 3-24
- "Configurations Tab" on page 3-32
- "Applications Tab" on page 3-35
- "Statistics Tab" on page 3-37
- "Notification Tab" on page 3-41
- "Print Tab" on page 3-46
- "Logging Out" on page 3-50

Starting the Sun Configuration and Service Tracker UI Console

Sun Configuration and Service Tracker 3.6.0 is installed as a stand-alone application which uses the Sun Configuration and Service Tracker applet for the user interface. The Sun Configuration and Service Tracker 3.6.0 GUI Console supports the following browsers:

- Netscape Navigator, version 4 or higher
- Mozilla and Firefox
- Any compatible browser version that supports the Java2 plug-in.

Note – If the Java2 plug-in is not installed on the system, the plug-in can be downloaded and installed from www.netscape.com. Systems running Solaris 8 or higher have Java 2 pre-installed.

Follow these steps to start the Sun Configuration and Service Tracker applet from your Internet browser.

To Start the Sun Configuration and Service Tracker UI Console

- 1. Open your Internet web browser.
- 2. In the Address field of your browser, type the following URL:

```
http://<serverhost.domain>/cst.html
```

OR

```
http://<serverhost.domain>/cstj2.html
```

Note – The <middlewarename.domain> refers to the name of the middleware server that has an HTTP daemon running and where the Sun Configuration and Service Tracker repository is maintained.

A Sun Configuration and Service Tracker login window displays as shown in FIGURE 3-1.

Eile Edit View Go Bookm	arks <u>T</u> ools <u>W</u> indow <u>H</u> elp		
Back Forward Reload St	op 🕼 http://sustain-13.central:8888/cstj2.html	Search	Srint - 🦉
👔 🟦 Home 🛛 🤡 Bookmarks 😂 Ja	va Desktop System 🔏 Sun Microsystems		
Sun Confi	guration & Service Tracker		
	601 Logia	1	
	User Name : cstadm Password : ***** Log In Clear		

FIGURE 3-1 CST Login

- 3. To log in, complete the following steps:
 - a. Type your user name, password.
 - b. Click the Log IN button.

The Sun Configuration and Service Tracker applet's main window is displayed in the browser (see FIGURE 3-2). The applet displays the hierarchy of the systems monitored on the left side and a history of events of the repository server with other details on the right side.

For further details and use of the applet, see "Console Views" on page 3-4.

Note – Depending on the group to which you belong (*cstadmin* or *cstops*) you have either READ and WRITE or READ ONLY privileges to the user interface. For more information about levels of user access based on group rights, refer to "User and Group Management" on page 4-2.

Console Views

The console displays all categories of data collected by Sun Configuration and Service Tracker. You can view and annotate events, compare configurations, enter custom information, compute statistics and print reports. The Sun Configuration and Service Tracker Console includes the Hierarchy view, as described in the "Enterprise Hierarchy Section" on page 3-24.

				Web Browser						•••
<u>Eile E</u> dit ⊻iew <u>G</u> o	Eile Edit View Go Bookmarks Iools Window Help									
Back Forward Re	🍋 🙆 🖅 http: aload Stop	//sustain-13.central:8	888/cstj2.html						Search Print	• 🔮
🚳 Home 🛛 🤡 Bookmar	ks 💜 Java Desktop S	ystem 🧷 Sun Micros	ystems							
Sur est - Agents - Agents - Agents - wrkt2-bs3-st2 - sustain-13.Central	Configuration & ite Info Records Config CST History Config 864 865 865 865 866 867 868 867 868 867 868 867 868 867 868 867 868 867 868 867 868 867 868 867 868 867 868 867 867	Service Track gn Custom Info urations Applications Software changes CST package up System shutdown System reboiled System available	System : susta System : susta Statistics No Event Sove rade	Refresh Lc in 13.Central Statu ottfication Print 07/11/2006 10 07/11/2006 10 07/27/2006 3 07/27/2006 3 07/27/2006 3 07/27/2006 3 07/27/2006 3	a Out Help_	tadm (Administra lp	tor) Planned 2 2 2 2 2 4 4	pdated at :	Tue Aug 01 17:37:19 Comment SUNWsrsep CTEact This is the last mes Version: CST3.6.0 -by cstadm System available in Seat. Get 1 stock	EDT 2006
	Event Cause Cod S) User Comments System available	e sstern Management - Pla in multi-user mode	nned/Scheduled Reboc	it	/pdate ppend Save Cancel					
	System Information	Installed Hardware	Software Packages	Software Patches	Solaris Internal Info	Custom Info	Volume Manager	Cluster		2
< > >	A	tion		Label		Description			Revision #	
🚯 🖂 🚳 📇 🐼	Loading Java Applet .							1		



The console is divided into three sections; TABLE 3-1 explains each section.

Section	Description
Banner and System Summary section	This section is at the top of the screen. The name of the selected system, its system status, and status of Sun Configuration and Service Tracker on that system is displayed. The banner section also includes two buttons: SITE INFO and CAUSE ASSIGN .
<i>Enterprise Hierarchy</i> section	This section is the left portion of the window. The hierarchical representation for all the Sun Configuration and Service Tracker agents on the CST Applet console only is displayed. When clicked, the agent hostname displays details about that system.
Tabs	This section is the bulk of the screen and is below the Banner and <i>System Summary</i> section. Select one of the six main tabs listed horizontally to display detailed information about the selected system. Specifics about the data included in each tab is explained later in this chapter.

TABLE 3-1 Console Sections

When a system is selected in the Enterprise Hierarchy section, all the sections in the Sun Configuration and Service Tracker console display information about the selected system. The only exception is the Global Cause code function, which is accessed by clicking the **CAUSE ASSIGN** button in the *System Summary* section that displays the information about outage events for all systems tracked by this Sun Configuration and Service Tracker installation.

System Summary Section

The *System Summary* section is located at the top of the Sun Configuration and Service Tracker console. It displays information about the selected system.

Note – Please note that if you click the **RELOAD** button of the web browser while viewing the Sun Configuration and Service Tracker GUI Console, the Sun Configuration and Service Tracker GUI restarts and displays the Sun Configuration and Service Tracker Login dialog box. You must re-enter your user ID and password to re-access the console.





TABLE 3-2 describes the elements included in the System Summary section, which is the top section of the window.

TABLE 3-2	System	Summary	section
-----------	--------	---------	---------

Field	Description
Refresh	Button that updates the System View or Enterprise View information.
	• The Enterprise View refreshes the entire set of data displayed in the Sun Configuration and Service Tracker UI, including the hierarchical information. The refresh can take a prolonged time depending on the size of the enterprise and on the status of the systems in the top level of the hierarchy.
	• The System View refreshes the details of the system whose name is displayed in the Summary section below the REFRESH button and which was selected in the Hierarchical section.
	Refreshing the Enterprise Hierarchical section reverts the display to the top level hierarchy only; the middleware system is selected and can be viewed in the System view.
Help	Button that displays information About Sun Configuration and Service Tracker, as well as details about installing and using Sun Configuration and Service Tracker.
[Username]	The login ID of the current user as entered in the Login dialog box for this session. The role of the user is displayed within brackets to the right of the user name.
Site Info	Button that displays the <i>Site Info Dialog</i> that enables you to enter Customer Contact, Sun Contact, and Site Registration information. For details, see "Site Information" on page 3-7.
Cause Assign	Button that opens the <i>Global Cause Code Update Dialog</i> that enables you to view all system failure or panic events for all systems tracked by the installed middleware, and to assign an event cause code to each individual event or to multiple events For details, see "Global Cause Code Assignment" on page 3-15.
Custom Info	Button that opens the <i>Custom Info Dialog</i> where you can enter system management information. Five categories of detailed information can be entered: Business Location, Asset Information, Service Information, System & Usage Information, and User Defined. For details, see "Custom Info" on page 3-18.

Field	Description
Selected System drop-down list	The name as entered by the customer during Sun Configuration and Service Tracker installation of the selected system is the first system displayed in the list. If other systems have been added during the Sun Configuration and Service Tracker installation, they are available in the drop-down list.
Status	The status of the highlighted system as of the last refresh. The status is either Up or Down.
Sun Configuration and Service Tracker Status	The status of the Sun Configuration and Service Tracker application on the selected system as of the time the selection was made. The status is either Up or Down.

 TABLE 3-2
 System Summary section

Site Information

The **SITE INFO** button (located in the upper left corner of the window) displays the *Site Info Dialog*. The system administrator should use this form to enter site information that is pertinent to the entire site supported by this middleware.

	Site Info Dialo		\ominus $+$ \times
	Java Applet V	Vindow	
Customer Contact Info	Sun Contact Info	Registration Info	
Company Name : Business Unit : Ticker Symbol : Street Address : City : State : Country : Zip/Postal Code :			
Customer Contact System Admin Contact	Alte	rnate Customer Cont	act
Name : Phone # : Pager # : Email ID :	Na Ph	me :	
Data Transfer Transmission of Data to Registration Status: Unr Transport Mode: None	Sun Microsystems, egistered Apply	Inc.: Disabled	

FIGURE 3-4 Site Info Dialog - Customer Contact Info tab

Site Info Dialog

The Site Info Dialog includes three tabs:

Customer Contact Info tab

Enables you to provide company and customer contact information. The Data Transfer section is static and indicates whether Sun Configuration and Service Tracker is configured to transfer event and configuration data to Sun Microsystems

Sun Contact Info tab

Enables you to enter Sun support contact information for the Sun Configuration and Service Tracker installation.

Registration Info tab

Provides various options and information that must be completed and submitted electronically to register your site.

Complete the following steps to provide required site, contacts, and registration information.

To Enter Site Information

1. From the Sun Configuration and Service Tracker Console, click the SITE INFO button.

The Site Info Dialog is displayed (see FIGURE 3-4)

- 2. In the Customer Contact Info tab, complete the following steps:
 - a. In the Company Information section, enter the appropriate information in the fields.

Field	Description
Company Name	Name of the company
Business Unit	Name of the business unit who is using the Sun Configuration and Service Tracker server.
Street Address	Street address of the company or business unit.
City	Name of the city where the street address of the company or business unit is located.
State	Name of the state where the street address of the company or business unit is located
Country	Country in which the company or business unit is located.
Zip/Postal Code	Postal code of the street address of the company or business unit.

b. Complete one of the following steps:

• If you are entering information for the first time, or need to enter information in additional tabs, proceed to step 3.

• If you have finished entering information, click one of the following buttons:

Button	Description
APPLY	Saves the contact information you have entered.
CLOSE	Closes the <i>Site Info Dialog</i> . If you fail to click the APPLy button before clicking CLOSE , your changes are discarded.

Note – If the customer site includes an installation of Sun Remote Services Net Connect version 3.2 or later, and if Sun Configuration and Service Tracker detects that transfer method, Sun Configuration and Service Tracker automatically uses SRS Net Connect 3.2 for its data transfer into the AMS database at Sun. If Sun Configuration and Service Tracker does not detect SRS Net Connect 3.2, the data is transferred via email.

3. Click the Sun Contact Info tab, and complete the following steps:

The Sun Contact Info tab is displayed (see FIGURE 3-5).

	Site Info Dialo		● ⊕ ⊗
	Java Applet V	Vindow	
Customer Contact Info	Sun Contact Info	Registration Info	
Primary Sun Contact Name : Phone # : Pager # : Email ID :			
Secondary Sun Contact Name : [Phone # : [Pager # : [Email ID : [
	0 mike (less	

FIGURE 3-5 Site Info Dialog - Sun Contact tab

a. In the *Primary Sun Contact* section, enter the appropriate information in the fields.

Field	Description
Name	Name of the primary Sun contact.
Phone #	Telephone number of the primary Sun contact.
Pager #	Pager number of the primary Sun contact.
Email ID	Email address of the primary Sun contact.

b. In the *Secondary Sun Contact* section, enter the appropriate information in the fields.

Field	Description
Name	Name of the secondary Sun contact.
Phone #	Telephone number of the secondary Sun contact.
Pager #	Pager number of the secondary Sun contact.
Email ID	Email address of the secondary Sun contact.

c. Complete one of the following steps:

- If you are entering information for the first time, or need to enter information in additional tabs, proceed to step 4.
- If you have finished entering information, click one of the following buttons:

Button	Description
Apply	Saves the contact information you have entered.
CLOSE	Closes the <i>Site Info Dialog</i> . If you fail to click the Apply button before clicking Close, your changes are discarded.

4. Click the *Registration Info* tab.

The *Registration Info* tab is displayed (see FIGURE 3-6).

	Site Info Di	alog	$-+\times$	
	Java Apple	et Window		
Customer Contact Inf	o Sun Contact Inf	o Registration Info		
Request Key				
Service Selection				
SunUp				
Other				
I Accept the term	s of the agreement	View Agreement		
Auto register usi	na CST local omail a	ecount?		
Muto-register usi	Registratio	n complete	8	
Re lava Applet Mindaw				
4	Java Appi			
x Registra	ation Successful.			
Please	restart the CST GUI	for changes to take effect	on the UI.	
	0	К		
Register Key				
Customer ID :	SUNW			
Registration Key :	075C-E122	-6BEE-7C7D		
		Destates	Class	
		Register	Close	

FIGURE 3-6 .Site Info Dialog - Registration Information tab

Note - Completion of the information in this tab is required to register your site.

- a. In the Service Selection section, click one of the following options:
 - SunUp—The Sun team that provides the user ID and registration keys that are used when the Sun Configuration and Service Tracker Server is registered with Sun.
 - Other—Indicates you are not using SunUp. Enter a short description in the text field of the service you are using.
- b. If you accept the terms of the Sun Service Agreement, click the I accept the terms of the agreement check box.

Note – To view the agreement, click the VIEW AGREEMENT button.

c. To auto-register your Sun Configuration and Service Tracker site, click the **Auto-register using CST local email account? check** box.

Using System Admin Contact email ID entered in the Customer Contact Info tab, a request is emailed to the Primary Contact person entered in the Sun Contact Info tab to notify Sun about the request to process the registration. After approval from the Sun Contact person, the Customer ID and Registration key is generated and provided to the Customer System Admin through email.

Note – The site can also be registered manually by contacting the Sun contact persons and obtaining the Customer ID and registration code.

d. To submit the registration and request for activation, click the **SUBMIT** button.

Note – The **HELP** button provides additional information about the options displayed on tab.

- 5. Click the **CLOSE** button until you have received your customer ID and Registration key.
- 6. Obtain the Customer ID and Registration key. For information, see "Site Registration" on page 4-5.
- 7. In the Customer ID field, enter your customer ID.
- 8. In the Registration Key field, enter the registration key.
- 9. Click the **REGISTER** button to save and send the registration information to Sun, and to then activate the data transfer to Sun:

Note – The Data Transfer option at the bottom of the *Admin* dialog box only displays for customer sites which have registered using this Site Registration function. Once the customer site is registered, the Data Transfer section in the *Customer Contact Info* tab reads *Enabled*.

Global Cause Code Assignment

You can define which events are tracked and reported by Sun Configuration and Service Tracker 3.6.0 by assigning a cause code to events. Assigning a Cause code to an event adds value to the Sun Configuration and Service Tracker data and increases the usability of your Sun Configuration and Service Tracker reports. By assigning the highest level of cause code, you can track which events were planned and which were not and to which category each defined event is assigned. Details in your Cause codes and your comments about the planned event (such as monthly maintenance of hardware, or application upgrade installation requiring system reboot) add value. Details about unplanned outages (such as electrical outages in the greater metropolitan area lasting five minutes, or database corruption requiring system down and backup restoration) can be even more valuable. Reports that include such details result in significantly improved recognition of trends and possible remediation.

A Cause code can be assigned to a single event, or it can be created and then assigned to multiple events.

Note – To define and assign a Cause to a single event, open the History tab and use the Event Cause code function. For more information, see "To Assign an Event Cause Code" on page 3-27.

Note – For details on assigning value-add Cause codes, refer to the *Best Practices Guidelines for Assigning the Correct Cause Code* document located at the following URL:

http://docs.sun.com/source/817-3765-01/index.html

To Globally Assign a Cause Code

If multiple outage system events are Undefined, and there is a common Cause behind those events, you can assign a Cause code to multiple events at one time.

1. From the Sun Configuration and Service Tracker Console, click the CAUSE ASSIGN button.

The *Global Cause Code Update* dialog box is displayed (see FIGURE 3-7). This dialog box displays all of the system outage events for all systems tracked by this middleware that occurred during the last 24 hours.

Sun Confi	guration & Service Tracker Refresh Log Out Help 🏠 cstadm (Administrator)	
Site Info	🛠 Cause Assign 💿 Custom Info System : sustain-13.Central Status : Up CST Status : Up	
Enterprise View	Up CST History Configurations Applications Statistics Notification Print	pdated at : Tue Aug 08 17:54:32 EDT 2006
Enterprise View Enterprise View Enterprise View CLUSTER, PLATFORM CLUSTER Statistical Science Code Statistical Science Code Statistical Science Code Statistical Science Code Sci	CST History Configurations Applications Statistics Notification Print Comment Prevent Date/Time Planned Comment Global Cause Code Update Counter Vindow Dava Applet Window Contract Cause Code Update Check HostName Hierarchy & Statistics Plann. Cause Code Deck HostName Hierarchy & Statistics Planned/Sche Uutage Events Deck HostName Hierarchy & Statistics Planned/Sche Uutage Events Deck HostName Hierarchy & Statistics Planned/Sche Uutage Events Deck HostName Hierarchy & Statistics Planned/Sche Uutage Event Cause Code Undefined Stelet. Apply Close	e Manager Cluster Revision #
	Apply Close	Revision ≇

FIGURE 3-7 Global Cause Code

- 2. To change the time period of displayed events, complete the following steps:
 - a. Click the time period drop-down list to display the available time periods.
 - b. Select the time period for which you want to view events (such as Last Quarter, and Last 24 Hours).
- 3. In the *Check* column, click the check box of the events to which you want to assign an Event Cause code.

Note – To select all displayed events, click the **SELECT ALL** button.

4. Click the **APPLY** button.

The *Event Cause Code Dialog* is displayed. For bigger installations it might take several minutes to completely display the window, as each agent data is checked for the outage event for the specified time period

16:36:22 EDT 2006
^
et Latest 🔽
<u>.</u>
3 G

FIGURE 3-8 Event Dialog in Global Cause Code Window

Note – The lists of Planned and Unplanned event Cause codes are identical to those used in the CST History Event Cause Code assignment process. To define a Cause Code to one event at a time, see "To Assign an Event Cause Code" on page 3-27.

5. To specify the appropriate Cause code, click the appropriate category tab:

Tab	Description
Undefined	Any event which is not a Planned or Unplanned event is designated as an Undefined event type.
Planned	Any event that the system administrator had planned in advance and notified other users about the event to minimize event impact. This information can be useful for computing system availability statistics.
Unplanned	Any event which the System Admin designates as "Not Planned." An unplanned event might be some host panic or any unplanned outage, or reboot, and similar types of events.

Note – If the *Global Cause Code Dialog* is not visible, move the window, which is in front, up or to the side until the **OK** button is visible.

- 6. Within the folder, select the appropriate Cause code or define a new code.
- 7. Click **OK** to save the definition of the cause for the selected events.

Custom Info

The *Custom Info Dialog* enables you to record system management information in five categories. This information is not required by Sun. Recording this information can enhance the internal service level for your systems.

The Custom Info Dialog includes five tabs:

- Business Location
- Asset Information
- Service Information
- System & Usage Information
- User Defined

This section contains the following topics:

• "System Selection" on page 3-19

- "Define Custom Fields" on page 3-20
- "Record Custom Information" on page 3-22

System Selection

To record system management information, you need to choose a system with which to work. The system you have selected in the Hierarchy section is the default system and is displayed in the Selected System field. You can work with this system or select a different system.

To Select a System

1. From the Sun Configuration and Service Tracker console, click the **CUSTOM INFO** button.

The Custom Info Dialog is displayed (see FIGURE 3-9).

	Custom Info D	ialog	-		Custom Info	Dialog	⊝⊗	
	Java Applet \	Vindow		Java Applet Window				
Selected System:	su	stain-13.Central.Sun.COM	-	Selected System: sustain-13.Central.Sun.COM				
Service Information	System & Usage Info	User Defined		Service Information	System & Usage li	nfo User Defined		
Business L	ocation	Asset Information		Business Lo	ocation	Asset Info	ormation	
Business Unit				Serviced By (Company	/Name)			
Sub-business Unit 1				Service Contract Leve	I			
Sub-business Unit 2				Service Contract ID				
Plant Name / ID				Contract Expiration Da	ite			
Location ID				Service Engineer Nam	e1			
Geo / Locale				Email Address1				
Building #				Phone1 #				
Floor				Pager1#				
Room/Lab #				Service Engineer Nam	e2			
Rack #				Email Address2				
Street Address				Phone2 #				
Street Address 2				Pager2 #				
City								
State / Province					Eart App	Close		
Country								
ZIP / Postal Code								
	Edit Önnbu	Class						
	Cuit Apply	Cluse						

Business Location & Service Information.



2. To work with another system, click the name of the system in the **Selected System** drop-down list.

This functionality is available on all from all five category tabs.

Define Custom Fields

The fields in four of the tab are comprehensive and based on input from many customers. The User Defined tab enables you to define information not included in the other tabs. If you have system management information that does not fit into the defined fields, you can define your own fields and enter your information in the User Defined tab.

To Define a Custom Field

1. From the Sun Configuration and Service Tracker console, click the **Custom INFO** button.

For more information, see "System Selection" on page 3-19.

2. From the Custom Info Dialog, click the User Defined tab (see FIGURE 3-10).

Sun Configu	ration & Service T	racker Refresh Log Ou	t Help 🌴 cstadm (Administrator)	
microsystems 🔘 Site Info 🔦	Cause Assign 🕘 Custom	nfo System : sustain-13.Central Status : U	lp CST Status : Up	
Enterprise View				Updated at : Tue Aug 08 16:41:15 EDT 2006
Enterprise	CST History Configura	Custom Info Dialog		
► Agents	# Event 677 Custom Info char	Java Applet Window	C(omment
← CLUSTER_PLATFORM ← CLUSTER	678 Software change:	Selected System: sustain-13.C	ientral.Sun.COM 🔽	
sustain-13.Central.Sun.COM	680 Software change:	Service Information System & U	Edit Field Names 🛞	
6	681 Software change: 682 CST package ren	Business Location	Java Applet Window	ed
E	683 CST package up(Label 1 Please	name your label:	
		Label 2		Service Event Get Latest 💌
		Label 3 Label 2		
	Event Cause Code	Label 4 Label 4		
		Label 5	j	
	User Comments	Label 6		
	Version: CS13.6.0 CST tracking started	Label 7		
		Label 8 Label 9		
		Label 1	0	
			OK Cancel	
	Configuration Changes	Label Edi		Lielune Manager Charter
	System information II		custommu	Pevicion #
	Action		1011	rcension #
	-			



FIGURE 3-10 User Defined tab - Label function

3. Click the LABEL button at the bottom of the screen to change the Label from "Label 1" to something more descriptive.

- 4. Click the **EDIT** button at the bottom of the screen to add the information in the Label.
- 5. Type the name of the label for each of the fields want to define.

Note – Each label name must be unique per machine.

6. Click **OK**.

This saves the label names and returns you to the User Defined tab.

- 7. Click the EDIT button and type the information for each labeled field.
- 8. To save the entered field contents, click the APPLY button.

The following sections provide details about entering data into the other tabs.

Record Custom Information

In the *Custom Info Dialog*, all fields are initially grayed out to enable you to read all previously applied information. There are three buttons at the bottom of the screen:

TABLE 3-3

Button	Description
Edit	Activates the write function for the fields on the displayed tab. Each tab is independent and clicking EDIT on one tab activates the write function in that tab only. The write function remains active on each activated tab until information in that tab is applied or until the <i>Cust Info Dialog</i> is closed with the CLOSE button. See Note below regarding availability of this functionality.
APPLY	Saves the information entered into the fields of the tab. The tab remains open until you click CLOSE . The information in each tab is independent and clicking APPLY in one tab saves the information in that tab only. Information not applied when the CLOSE button is clicked is discarded; to save the data, be sure to click APPLY on each tab before you click the CLOSE . button.
CLOSE	Closes the Cust Info Dialog. Any data not applied (saved) on any tab is discarded.

Note – When users are set up by the Sun Configuration and Service Tracker administrator, two types of users can be established: those with full access to READ and WRITE, and those with READ ONLY access. READ ONLY users can view all previously applied data for a selected system, but the **EDIT** and **APPLY** buttons are not functional.

To Record Custom Information

1. From the Sun Configuration and Service Tracker console, click the **Custom INFO** button.

For more information, see "System Selection" on page 3-19.

- 2. In the *Custom Info Dialog*, click the tab in which you want to enter or edit information.
- 3. Click the **EDIT** button to activate the write function for the tab.
- 4. Enter system information into the applicable fields.
- 5. When all information has been entered, click the **APPLY** button to save the information in that tab.
- 6. To change to another tab, click on that tab and repeat steps 3 through 5.

Note – Entered information is saved only when you click the **APPLY** button on the displayed tab. Any information not applied is discarded when the *Cust Info Dialog* is closed.

- 7. When you have completed entering and saving all information, click **CLOSE**. The *Cust Info Dialog* closes.
- 8. To enter custom information for another system, repeat steps 1 through 7.

Enterprise Hierarchy Section

The Enterprise Hierarchy section displays the complete enterprise hierarchy view of the various systems tracked by this Sun Configuration and Service Tracker server. The hierarchical view is a graphical tree structure that can be expanded and collapsed by clicking on the desired system.



FIGURE 3-11 The Enterprise Hierarchy section

There are six system folders, also called tab folders. The tab folders display information about the selected agent system. The following sections describe the folders in detail.

Sun Configuration and Service Tracker History Tab

The main Sun Configuration and Service Tracker History tab displays present and past system information in its three sub-sections.

- The top section of the tab lists the event information, which includes the event number, event description, date/timestamp, whether the event was planned or un-planned, and comments entered by the user.
- The events are displayed chronologically and in ascending order (most recent event last). Only the first few words of the comments are displayed in the comment column.

- The middle section of the folder displays any assigned event Cause Code and the full text of the comment associated with the current selected event. In addition, you can modify both the Cause code and the comments.
- The bottom section displays the configuration changes, if any, associated with the selected event.

Sun Config	uration & S	Service Tra	cker		Refresh Log	Dut Help	🛧 cstadm (Admini	strator)			
microsystems 🗿 Site Info 🖇	Cause Assign	🛞 Custom Inf	io Syst	em : sustain-13.Cen	tral Status :	Up CSTS	tatus : Up				
Enterprise View			V	- V V			_		Updated at :	Tue Aug 08 1	6:41:15 EDT 2006
Enterprise	CST HIStory	Configuration	s Application	s statistics	Notification	Print		0			
o- Agents	# 677 Cust	Event tom Info changes	08/03/20	Date/Time 06 08:13:14	?			Com	ment		
← CLUSTER_PLATFORM	678 Softv	ware changes	08/04/20	06 13:06:59	?	SUNWj5rt					
sustain-13.Central.Sun.COM	680 Softv	vare changes vare changes	08/04/20	J6 13:12:01 36 13:17:07	?	SUNWaw	c.				
	681 Softv	ware changes	08/04/20	06 13:22:19	?	SUNWcac	ao				
	682 CST	package remove	08/04/20	06 13:30:36 06 13:31:04	?	This is the	last message until C	3T is re-installed			
	000 1001	package upgrau	5 00/04/20	10 10:01:04	1	Version. C	010.0.0				▼
									Service E	vent Ge	t Latest
	Event Ca	ause Code				_					
			Unde	ined		0	pdate				
	User Co	mments									
	Version	: CST3.6.0				A	opend				
	CST trai	cking started					Bave				
							oncol				
	· · · · · · · · · · · · · · · · · · ·						ancer				
	Configuration	Changes									
	System Info	rmation Insta	led Hardware	Software Package	s Software I	Patches	Solaris Internal Info	Custom Info	Volume Manager	Cluster	
		Action		La	abel		Descrip	tion		Revision #	

FIGURE 3-12 CST History Tab

TABLE 3-4 CST History Tab Section

Section	Description
Event list	The list of events is specific to the selected system. The number for each event is static as the number is assigned when the event is generated and is connected with the history for the selected system. The name of the event comes from a list of standard Sun Configuration and Service Tracker tracked events. The timestamp is attached to the event when the event occurs and is recorded in the database. If Sun Configuration and Service Tracker cannot identify whether the event was planned or unplanned, a question mark is populated into the field by default. You can define the details of the event in the Event Cause Code section. To further define the event, you can enter comments pertaining to the cause, resolution, and other details that would be valuable in current and future event analysis and resolution. For information about entering comments, see "To Add Comments to an Event" on page 3-29.
Get Latest dialog	To control the displayed events, click the Get Latest drop-down list. The choices in the drop-down list are: Get Latest, Get Previous 10, and Get All Events.

This section includes the following topics:

- "To View Different Events" on page 3-26
- "To Assign an Event Cause Code" on page 3-27
- "To Add Comments to an Event" on page 3-29
- "To Create a Service Event" on page 3-29
- "To Look Up Configuration Changes" on page 3-30

To View Different Events

The events initially displayed when you first bring up the Sun Configuration and Service Tracker console are the most recent events for the selected system. The **GET LATEST** drop-down list located below the list of events enables you to control which events are listed. To view events, complete the following steps:

- 1. From the Sun Configuration and Service Tracker Console, click the main *CST History* tab.
- 1. Click the **Get Latest** drop-down list, and choose the **Get All Events** to pull all events from the repository and display them.

Note – The **Get All** function can take a significant amount of time to complete depending on the total number of stored events for the selected system.

To Assign an Event Cause Code

You can add value to a single event that is listed with a question mark in the Planned field by assigning an Event Cause Code. To assign an Event Cause code, complete the following steps:

- 1. From the Sun Configuration and Service Tracker Console, click the main *CST History* tab.
- 2. Click the **UPDATE** button in the right side of the *Event Cause Code* section of the screen.

The *Event Cause Code* dialog box is displayed (see FIGURE 3-13).

3. Choose the appropriate tab from which to assign an *Event Cause Code*:

Tab	Description
Undefined	Any event which is not a Planned or Unplanned event is designated as an Undefined event type.
Planned	Any event that the system administrator had planned in advance and notified other users about the event to minimize event impact. This information can be useful for computing system availability statistics.
Unplanned	Any event which the System Admin designates as "Not Planned." An unplanned event might be some host panic or any unplanned outage, or reboot, and similar types of events.



FIGURE 3-13 Cause Code Assignment Dialog Screens

4. Select the appropriate category and cause for the event from the drop-down list.

Note – If an event is neither Planned or Unplanned, it automatically falls to "Undefined" category.

5. Click APPLY.

To Add Comments to an Event

You can append a comment to a specific event. To add a comment, complete the following steps:

- 1. From the Sun Configuration and Service Tracker Console, click the main *CST History* tab.
- 2. Click the **APPEND** button.

The Comments dialog box is displayed.

- 3. Type the comment you wish to add to the event.
- 4. Click the **SAVE** button.

The comment displays in the **Comment** field of the event. The login ID of the session is appended to the comment.

Note – After selecting the **APPEND** button, click inside the User Comments window to enable writing.

To Create a Service Event

You can create a custom Service Event in the *CST History* tab. Service engineers or system administrators use the **SERVICE EVENT** button to capture any specific action or information about the system that might be useful for future reference. To create a Service Event, complete the following steps:

1. From the Sun Configuration and Service Tracker Console, click the main *CST History* tab.

The Service Event section is located in the middle area of the tab.

- 2. Click the **Service Event** button.
- 3. In the *Comments* dialog box, type an event description.
- 4. Click the **SAVE** button to create a service event.

The Event description will be User's Service.

The new event automatically displays in the event log.

Note – Service engineers should use this feature every time they service a system as these events can provide a useful audit trail describing the actions taken on the system.

To Look Up Configuration Changes

The *CST History* tab contains the Configuration Changes section that is located at the bottom of the window and contains several tabs. When you select an event, these tabs contain information about configuration changes that were detected at the time the event occurred. The names of the tabs are identical to the name of the associated configuration files:

- System Information
- Installed Hardware
- Software Packages
- Software Patches
- Solaris Internal Info
- Custom Info

The fields vary according to the tabs, and their labels are indicated just above each data section (see FIGURE 3-14).
Sun Configuration	& Servi	ce Tracker		Refn	esh Log Out	Help	🛧 cstadm	(Administrator)				
microsystems 🕜 Site Info 🔍 Cause As	ssign 🔘 C	ustom Info	ystem : sustain	13.Central	Status : U	p CST	Status : Up					
Enterprise View	007.0	0.5 ľ	V		V 11-075		V Bit		Updat	ed at : Wed Aug I	09 17:12:08 E	EDT 2006
Entornriso	UST HISTO	ry Configurations	Applications	Statistics		ation	Print					
o-Anents	#	Event	D	ate/Time	Pla	nned			Comment			
- nwk12-bs3-s12.sfbav	677 C	ustom info changes	08/03/2006 (18:13:14	?		OLIN BASZ 4					_
- sustain-12	670 9	offware changes	08/04/2006	3.00.09	2	10	SUNWJ911 SUNWJ900					
← CLUSTER_PLATFORM	680 S	offware changes	00/04/2000	3:17:07	?		SUNWasvc					_
- CLUSTER	681 S	oftware changes	08/04/2006 1	3:22:19	?		SUNWcacao					
- sustain-13.Central.Sun.COM	682 C	ST package remove	08/04/2006 1	3:30:36	?		This is the las	t message until CST i	s re-installed			
	683 C	ST package upgrade	08/04/2006 1	3:31:04	?		Version: CST3	1.6.0				-
									S	ervice Event	Get Latest	-
	Even	t Cause Code	1 had a fear	- 4								
			Undefin	ea			Upc	ate				
	User	Comments										
	SUN	Wj5rt					App	end				
							Sa	1/10				
							Car	ncel				
	-Configurat	ion Changes										
	System I	nformation Installe	d Hardware	Software P	ackages	 Softw 	vare Patches	Solaris Internal Info	Custom Info	Volume Man	ager Clus	ster
		Action					ID			Description		
	Replaced			Patch	n: 114049-11			Ob	soletes: Require	s: Incompatibles	: 114045-02	Pack
	by			Patch	n: 114049-11			Ob	soletes: Require	s: Incompatibles	: 114045-02	Pack
	Replaced			Patch	n: 115926-08	}		Ob	soletes: Require	s: Incompatibles	: Packages:	SUN
	by			Patch	115926-08	3		Ob	soletes: Require	s: Incompatibles	: Packages:	SUN
	Added			Pater	1:119211-05)		Ob	soletes: 115926-	10, 117724-10 Ri	equires: inco	impat
	Audeu			Pater	1. 110837-02	-		10	soletes. Require	s. incompatibles	. Packages.	SUN
	Added			Pater	1:118666-03	3		dU	soletes: Require	s: incompatibles	: Packages:	SUN
	P											

FIGURE 3-14 Configuration Changes in the History Folder

To look up configuration changes, complete the following steps:

- 1. From the Sun Configuration and Service Tracker Console, click the main *CST History* tab.
- 2. Select the event for which you want to see configuration changes.
- 3. In the *Configuration Changes* section, click the appropriate tab to view the configuration changes associated with the selected event.

Note – A bullet next to the tab name indicates that the tab contains data.

Configurations Tab

The man Configurations tab describes the past and present hardware and software configurations of the system. You can select one of the following configuration options (see FIGURE 3-15):

- Current configuration
- Inception configuration

Iew	CST History Configurations Applications Statisti	s Notification Print			
	Configuration Selection				
12-bs3-s12	Current Inception				
ain-12	System Information Installed Hardware Software Da	karge / Software Batches / Solaris Informal Info / Volume Ma	namer Cluster		
13.Central		Description			
	System Model	Sun Fire V120 (UltraSPARC-Ile 648MHz)	Revision #		
	Kernel Architecture	sun4u			
	OS Type	SunOS	5.9 Generic 118558-06 64-bit		
	Host Name	sustain-13			
	Host Aliases	sustain-13.central.sun.com loghost			
	Host Address(es)	172.20.6.180			
	Host ID	835c90a3			
	DNS Domain	central.sun.com			
	NIS Domain	notcorp.Central.Sun.COM			
	Serial Number	2203881635			
	Main Memory	1024 MB			
	Total Disk Space	67.8 GB			
	Total Disks	2			
	Total Cdroms	1			
	ROM Type	OBP	4.0.12 2002/01/08 13:01		
	Number of CPUs	1			
	CPU Type	sparc			
	Timezone	US/Mountain			
	Boot Time	Tue Jun 6 15:09:34 MDT 2006			
	MAC Address	0:3:ba:5c:90:a3			
	CST Version	3.6.0			
	Net Connect proxy Version	001.002.006			
	CST Identity	2:sustain-13:Server:3.6.0:::3.5.1			
	Net Connect Customer Id	49			
	Sun Management Center Version	NOTFOUND			
	Locale - LC_ALL	C			

FIGURE 3-15 Configurations/System Information Folder

- The Current configuration option shows information that was recorded immediately after the most recent event on the selected system.
- The Inception configuration option shows information that was recorded at the time Sun Configuration and Service Tracker was first installed on the selected system.

For each option, there are several tabs that contain different categories of configuration information.

 TABLE 3-5
 Configurations Folder Sections

Tab	Description
System Information	Displays the machine-populated specifications on the selected system, such as ROM type, and Host Name.
Installed Hardware	Lists all hardware detected by Sun Configuration and Service Tracker including details in the following fields: Label, Description, Part #, Revision #, Serial #, Hierarchy, and Other. A blue dot in the Other field indicates there are other details about the installed hardware not displayed in this tab.
Software Packages	Lists all software packages detected by Sun Configuration and Service Tracker including details in the following fields: Label, Description, and Revision #. The packages are listed in alphabetic order within the Label field.
Software Patches	Lists each software patch installed on the selected system (including details) from inception to the current time.
Solaris Internal Info	Lists all the parameters available within your Solaris OS with the assigned values. For example, the size of virtual address cache is listed with its assigned value.
Volume Manager	Displays the disk media, disk groups, volumes, plexes and sub disks for systems where volume manager is installed.
Cluster	Displays the cluster summary information, member status, resource list, resource type, resource group, resource, transport path, and quorum votes for systems that are part of Sun clusters.
Custom Info	Displays custom information you entered pertaining to system management data. For more information, see "Custom Info" on page 3-18, for details.

Applications Tab

Application Tab (see FIGURE 3-16) enables you to view information tracked on supported applications. The Application tab displays three sub-sections for the selected application. The following table (see TABLE 3-6) describes each section of the *Application* tab.

Screen Element	Description
Тор	Displays the name of the selected application for which the information is displayed, and the up/down status for that application. You can select a different application to view the data by clicking on the SELECT button and selecting the application. See next section for details.
Middle	Lists the event information, which includes event number, event description, timestamp and comments recorded by the Sun Configuration and Service Tracker agent.
Last	Displays the inventory and usage configuration (depending on the user selection) for the selected application.

TABLE 3-6 Application tab sections

Note – Not all inventory and usage information is available for all applications.

To View Application Information

Sun Configuration and Service Tracker 3.6.0 tracks Sun Java System applications and other classes of applications. Follow these steps to select the application to review.

- 1. Select the system name to be reviewed.
- 2. Click on the Application tab.

The Application tab displays qualifying events for the tracked applications for the selected date range and selected system.

3. To select a different application, click the **SELECT** button located in the upper left section of the screen.

A series of drop-down menus allows you to drill down through four layers to select the exact application to be reviewed: Class of application, Name of application and its version number, and the application instance.

- 4. Click the instance.
- 5. To view a different date range of data on the selected application, click the GET LATEST button. Select from the three choices:
 - Get Latest
 - Get Previous 10
 - Get All Events

#	Event	Date/Time		Comment	
1	Application REGISTERED	08/04/2006 13:12:10	?	Comment	
2	Application DOWN	08/04/2006 13:12:12	?		
L.					Get Latest
Configurati Invento	on Selection ry 🔘 Usage				
		Label		Description	
Product Clas	38			Sun Java System	
Product Nam	ne			Web Server	
roduct Vers	ion			6.1	
Product Insta	ancelD			https-admserv	
roduct UUIE	D			urn:uuid:c14a8732-bab2-487f-a886-78ffe1234930	
nstallation D	Directory			/opt/SUNW/wbsvr	
nstallation T	ime			08/04/2006 13:09:58	
Server Name	9			https-admserv	
Configuration	n Directory			/opt/SUNW/wbsvr/https-admserv	
Ittp Listener	r			ls1	
Ittp Port				8889	
				off	

FIGURE 3-16 Application tab

Statistics Tab

The statistics tab, shown in FIGURE 3-17, presents statistics for your review through its two components:

 TABLE 3-7
 Statistics tab components

Components	Description
System statistics	Displays the uptime statistics for the selected system.
Application statistics	Displays statistics for the selected application on the currently selected system.

ptime Statistics						
					Perio	od : Since Incept
					From: 06/02/20	103 To: 08/04/20
						Get Statistics.
		Total Tin	e (D:H:M:S) : 1158:15:3	0.31		
		Time L	lp (D:H:M:S) : 1150:13:2	0:13		
		Time Dow	n (D:H:M:S) : 8:2:19:18			
			Up %: 99.3012			
			Down % : 0.6988			

FIGURE 3-17 Statistics tab

TABLE 3-8	Statistics	tab
-----------	------------	-----

Sections	Description
GET STATISTICS button	Define the time period for the statistics displayed with the GET STATISTICS button and by selecting the appropriate time period from the popup window, as in FIGURE 3-17. The statistics for that date range display in the Statistics folder, with the date range displayed on the left side.
Selected Period	The period, From and To dates display the selected time period for which the displayed statistics apply. The default is This Week. To change, click the GET STATISTICS button.
Total Time	The total time for which these statistics apply.
Time Up	Time Up—the accumulative time in days, hours, minutes, and seconds that the system was up. A system is up when one or more of the following events occur: Processes such as the Sun Configuration and Service TrackerCST daemon and CST heartbeat daemon are executing.Interprocess communication is enabled (CST and the CST heartbeat daemons communicate with each other through IPC at regular intervals).Disk access to the system disk is functional as the CST heartbeat writes the timestamp into the system disk at regular intervals.
Time Down	The time when the system was down. For example, the Solaris OS kernel was not running or not executing processes, or the basic interprocess communication or disk access was not enabled.
Up %	The ratio of Time Up to Total Time expressed, as a percentage.
Down %	The ratio of Time Down to Total Time expressed, as a percentage.

Note – Statistics do not include downtime events (panic or shutdown) that have been marked as Planned. The amount of planned downtime on a system is not calculated in either the Time Down or Total Time figures. For instance: if a system's statistics cover 100 hours, two of which were marked as Planned downtime and two of which were unplanned shutdowns or panics, the Sun Configuration and Service Tracker statistics report shows that the system was up for 96 out of 98 hours— a 0.9796 Up%.

System Statistics

To view statistics on the currently selected system, complete the following steps:

1. Select the system name from the Enterprise Hierarchy Panel.

- 2. Click the *Statistics* tab.
- 3. In the Statistics tab, click the *System* tab.

The system statistics initially displayed are for This Week. The dates are displayed on the left side of the screen.

- 4. To select a different date range, click GET STATISTICS and select from the displayed list.
- 5. To view statistics for another system, repeat steps 1 through 4.

Statistics Dialog	Period : Since Inceptio From : 06/02/2003 To : 08/04/200
Java Applet Window	Get Statistics
Please choose from one of the following options Last 24 Hours This Week Last Week This Month Last Month This Quarter Last Quarter This Year Since Inception Customize From: Imm/dd/ywy To: Imm/dd/ywy OK Cancel	UP Statistics PHMS): 1158:15:39:31 PHMS): 1150:13:20:13 PHMS): 82:19:18 PHMS: 93:90:12 PHMS: 98:98 PHMS: 06988 PHMS: 0698 PHMS: 06988 PHMS: 0698 PHMS:

FIGURE 3-18 Statistics tab - System Statistics

Application Statistics

Sun Configuration and Service Tracker 3.6.0 tracks up and down events for supported software. To view the statistics for supported applications detected on the selected system, follow these steps.

CST History	Config	urations	Application	s Statistics	Notification	Print					
System A	plication										
Uptime Statis	ics										
Select: Su	n Java Si	/stem.Web	Server,6.1,h	ttps-admserv						Period :	This Week
Sun Java S	/stem →	Directory	Server,5.2						From : O	3/06/2006 To: I	ายกดุ/วิทาค
		Web Serv	ver,6.1	https-admserv						Get S	tatistics
				https-sustain-1	3.Central.Sun.COM	1				0000	tutiotico
				I	otal Time (D:H:M:S):3:8:35:24	1				
					Time Up (D:H:M:S	;): 0:0:0:0		 			
				Ti	me Down (D:H:M:S	():3:8:35:24	1				
					Down	%:0.0000 %:100.000	1				
					DOWN	. 100.000					

FIGURE 3-19 Statistics tab - Application Statistics

Sun Configuration and Service Tracker 3.6.0 tracks up and down events for supported software. To view the statistics for supported applications detected on the selected system, follow these steps.

1. Select the system name from the Enterprise Hierarchy panel.

- 2. Click on the *Statistics* tab
- 3. Click on the *Application* tab.
- 4. Click the **SELECT** button.
- 5. Choose the application for which you want to view statistics.

The system statistics initially displayed are for This Week. The dates are displayed on the left side of the screen.

6. To select a different date range, click **GET STATISTICS** and select from the displayed list.

Notification Tab

The *Notification* tab enables system administrators to configure different user email addresses for email notifications on selected events:

CST History	Configurations	Applications	Statistics	Notification	Print							
Email Recipient	s			1								
virendra sinc	n/@sun com					 	 	 				_
Au cum granif	n@surcon											
										Add	De	lete
Evente Acciano	d											
LVCIIIS ASSIGNC												_
CST attach Software cha	annes											
Subsystem F	PANICed											
Sun Java Sys	stem,Application S	erver UP										
											Mod	64
											MOG	iy

FIGURE 3-20 Notification tab

Note – If this tab is disabled, it means that either the agent Sun Configuration and Service Tracker is down or the agent Sun Configuration and Service Tracker is of a lower version and does not support this operation.

Section	Description
Email Recipients	Displays all email addresses configured into the system to receive email notifications from the agent.
ADD and DELETE buttons	Buttons that enable system administrators to create and delete an event list to email address mapping.
Events Assigned	Displays the events for which the email notifications are desired for every email address in the list displayed in the Email Recipients section.
MODIFY button	Button that opens a dialog box where system administrators can modify an event list that is attached to the selected email address.

 TABLE 3-9
 Notification tab

This section contains the following topics:

- "To Add a New Email to Event-list Mapping" on page 3-43
- "To Delete an Email from Event-list Mapping" on page 3-44
- "To Modify an Email-to-Event-list Mapping" on page 3-44

To Add a New Email to Event-list Mapping

You can select one or more events for which you want a notification email sent to one or more email addresses. You can email events in the following catagories:

- Outage Events
- System Events
- Cluster and Volume Manager Events
- Other Events
- 1. From the Sun Configuration and Service Tracker Console, click the main *Notification* tab.
- 2. Click the ADD button.

The Selective Email Dialog is displayed (see FIGURE 3-21).

FIGURE 3-21 Selective Email Dialog Window

- 3. From the Events lists, click the one or more events.
- 4. Click the >> button.

The selected event is moved to the Selected Events list box.

- 5. To add all events to the Selected Events list box, click the ADD ALL button.
- 6. In the assign Email field, type one or more email addresses.

Note – If you are entering more than one email address, separate them by a comma.

7. Click the APPLY button; click OK in the resulting confirmation dialog.

The email-to-event-list mapping is displayed in the main Notification tab.

Note – To discard your changes, click the **CANCEL** button.

To Delete an Email from Event-list Mapping

- 1. From the Sun Configuration and Service Tracker Console, click the *Notification* tab.
- 2. In the Email Recipients list, select the email address for which the mapping is to be deleted.
- 3. Click the **DELETE** button and the **OK** button in the resulting confirmation dialog.

To Modify an Email-to-Event-list Mapping

Use this function to change events for which notification is sent to an already identified email address.

- 1. From the Sun Configuration and Service Tracker Console, click the main *Notification* tab.
- 2. Click the email-to-event-list mapping that you want to modify in the the Events Assigned list.

3. Click the **Modify** button.

The *Selective Email Dialog* with the email address in read-only mode is displayed (see FIGURE 3-22). You can edit only the associated event-list.

FIGURE 3-22 Event-list Email Modification Window

- 4. Modify the event list by adding to or deleting events from the Selected Events list using the appropriate buttons.
- 5. Click the APPLY button; click **OK** in the resulting confirmation dialog.

/

Print Tab

From the *Print* tab you can retrieve, print, and send simple reports based on the system event and configuration for the selected system. The reports are sent to the designated email addresses.

Report Selection CST History © Selected Event All Events © Ennal Address: Printer : Printer : Apply	CST History	Configurations	Applications	Statistics	Notification	Print			
CST History Configurations Selected Event All Events Transmit Data to Email Address: Printer: 	Report Selection	on							
	CST History	Configurations	Ī						
Transmit Data to	Selection	ed Event 🔾 All Ev	rents						
Printer: Apply	Transmit Data	to				1		 	
Printer: Apply	Cindi Adu	1033.							
Арріу									
									Apply

FIGURE 3-23 Print tab

To Specify a History Report

TABLE 3-10 provides descriptions of the sections found in the CST History tab of the Sun Configuration and Service Tracker Console *Print* tab.

TABLE 3-10	Print tab -	CST	History	tab	sections
------------	-------------	-----	---------	-----	----------

Sections	Description
CST History tab	To print a report on Sun Configuration and Service Tracker events, click on this folder within the Print folder.
SELECTED EVENT and ALL EVENTS buttons	After you select CST History, click one of the radio buttons to specify the events to be included in the report. Click Selected Events to print a report including only event you have selected in the CST History tab. Click All Events to print a report including all events displayed in the CST History tab.
Configurations	To print a report of the configuration of the selected system, click on the Configurations tab and select from the displayed choices.
Current Configuration, Inception Configuration	Click on one of these radio buttons to specify the which events are to be included in the report.
	Current: prints the data which apply to the current system.Inception: prints the data which applied to the system when Sun Configuration and Service Tracker was initially loaded and run.
Categories	Select the category of data to be included in the report. One up to all of the categories can be selected. The categories that do not apply to the selected system can be selected, but an error displays telling you the category of data cannot be found. The balance of the report is sent to the indicated destination.
Transmit Data to	 Select the appropriate destination for the report. Email Address: Type the email address of the recipient of the report. You can enter multiple email addresses separated by a comma but no spaces
	 Printer: Type the name of a printer that is recognizable by the Sun Configuration and Service Tracker middleware.
	• Sun Microsystems: If this is an AMS version of Sun Configuration and Service Tracker, this pushes the report to Sun Microsystems into the established AMS database. If no AMS connection has been established, this option is not available.
Apply, Cancel	To process the selection, generate the report, and send it to the indicated destination, click the Apply button. To discard the selections and entered destination, click CANCEL .

- 1. When you want a report on only one event, highlight that event in the main *CST History* tab.
- 2. Go to the *Print* tab.

- 3. Select the CST History tab within the Print tab.
- 4. Click either the Selected **EVENT** or **ALL EVENTS** option (see FIGURE 3-23). The event report is generated.

Note – Note – The option to transmit data to Sun Microsystems displays only for customer sites which have registered using the Site Registration function

CST History Configurations App	lications Statistics Notification Print	Updated at : Fri Aug 04 11:25:53 EDT 2
Report Selection		
CST History Configurations		
Configuration Selection		
Current Configuration O Incepti	ion Configuration	
Categories		
System Information	✓ Installed Hardware	✓ Software Packages
Software Patches	✓ Solaris Internal Info	Volume Manager
Cluster Configuration	FRU Information	🖌 Custom Info
	2 All Configuration Information	
	P Air Conlight atom information	
ransmit Data to		
Email Address:		
O Printer -		
U THINK T		
		Apply Canc

FIGURE 3-24 Print - Configurations Folder

Note – The option to transmit data to Sun Microsystems displays only for customer sites which have registered using the Site Registration function. To Specify a Configuration Report1.Select the Configurations folder within the Print folder.

To Specify a Configuration Report

- 1. Select the Configurations folder within the Print folder. From the main *Print* tab, click the Configurations tab within the main *Print* tab.
- 2. Select either the CURRENT CONFIGURATION or INCEPTION CONFIGURATION button (see FIGURE 3-26).
- 3. Select one of the following categories:
 - System Information
 - Installed Hardware
 - Software Packages
 - Software Patches
 - Solaris Internal Info
 - Volume Manager
 - Cluster Configuration (unsupported in this release)
 - FRU Information
 - Custom Info.

The configuration report is generated.

To Print or Email a Report

- 1. To send the report as an email message, select the EMAIL ADDRESS button and type the desired email recipient.
- 2. To send the report to a printer, select the PRINTER button and type the printer name.

Note – To print a report, you must type the name of a printer that the middleware is configured to recognize.

- 3. To send the report directly to Sun, select the **SUN MICROSYSTEMS**, **INC**. radio button
- 4. To send the report to a printer or send it as email, after selecting the type of report, click the **APPLY** button.
- 5. To clear and discard your entries, click the CANCEL button.

Logging Out

To enhance security of your tracked data, you should log out of the Sun Configuration and Service Tracker Console when you are finished working with your data.

A Carao	Sun Con	figuration & S	ervice Tracker		Refresh	Log Out	Help	🛧 cstadm (Administrator)	
Microsystems	🕘 Site Info	🔍 Cause Assign	🔘 Custom Info	System : sustain-13.Cent	ral Sta	Exit	CST St	atus : Up	
Enterprise View	-								Updated at : Wed Aug O

To Log Out

- 1. In the Sun Configuration and Service Tracker Console, click **Log Out** in the top bar of the window.
- 2. In the drop-down list, click **Exit** to close the Sun Configuration and Service Tracker session.

Chapter 4

Sun Configuration and Service Tracker Administration

This chapter provides an overview of the Sun Configuration and Service Tracker software for version Sun Configuration and Service Tracker 3.6.0. It includes the following sections:

- "Authentication" on page 4-1
- "User and Group Management" on page 4-2
- "Site Registration" on page 4-5
- "Network Protocols" on page 4-9
- "Tuning Sun Configuration and Service Tracker Trigger Intervals" on page 4-11
- "Sun Configuration and Service Tracker Detach" on page 4-14
- "Sun Configuration and Service Tracker Tracking During OS Upgrades" on page 4-15
- "Managing Hierarchy" on page 4-16
- "Service and Cause Code Updates" on page 4-19

Authentication

Prior to starting the Sun Configuration and Service Tracker user interface, you must ensure the login user name is added to the appropriate Sun Configuration and Service Tracker group by the Sun Configuration and Service Tracker system administrator for that site. Refer to "User and Group Management" on page 4-2

for details. Depending on the group to which the user name is added, the user will have specific READ or READ & WRITE privileges through the user interface.

When a user logs in, Sun Configuration and Service Tracker authenticates the login with the assigned Sun Configuration and Service Tracker group. For further explanation, see "User and Group Management" on page 4-2.

User and Group Management

User and Group Management Access control is implemented to enhance security when viewing and annotating data. This security feature allows only authenticated users to view and annotate the Sun Configuration and Service Tracker data by providing a login session when a user accesses the Sun Configuration and Service Tracker console or applet. The user must have a Unix login account on the middleware host in order to access Sun Configuration and Service Tracker data. When prompted to enter a user name and password, the user logs in to the host through the login Unix command.

Each Sun Configuration and Service Tracker 3.6.0 user is assigned a login and a user access level.

Sun Configuration and Service Tracker Access Control List (ACL)

In addition to the user name and password check, Sun Configuration and Service Tracker includes its own access control. Each user belongs to a group: cstadm or cstops.

- cstadm users have read and write privileges to Sun Configuration and Service Tracker data
- cstops users have read-only privileges to Sun Configuration and Service Tracker data

To Create a cstadm or cstops Group

1. On the server system, log in as a superuser.

2. To create the desired group, type one of the following commands:

/usr/sbin/groupadd cstadm

or

/usr/sbin/groupadd cstops

To Add a User to a cstadm or cstops Group

- 1. Open the /etc/group file in a file editor.
- 2. Add the user's login name to the cstadmin or cstops group in the /etc/group file.
- 3. Save the file and exit the editor.

The following is a sample /etc/group file:

root::0:root other::1: bin::2:root,bin,daemon sys::3:root,bin,sys,adm adm::4:root,adm,daemon uucp::5:root,uucp mail::6:root tty::7:root,adm lp::8:root,lp,adm nuucp::9:root,nuucp staff::10: daemon::12:root,daemon sysadmin::14: smmsp::25:smmsp nobody::60001: noaccess::60002: nogroup::65534: ncgroup::100:ncuser mysql::104: cstops::106:cstusr cstadm::107:cstadm

The cstadm and cstops user levels have access to all privileges in the Sun Configuration and Service Tracker console. See TABLE 4-1 for a complete list of access levels and permitted actions.

Sun Configuration and Service Tracker Access Levels

The following tables details the tasks that can be performed in Sun Configuration and Service Tracker and indicates which groups are allowed to perform each task.

Task Performed in Sun Configuration and Service	Allowed to cstops	
Tracker	User	Allowed to cstadm user
Select a system to view status, CST status)	Х	Х
Bring up the Sun Configuration and Service Tracker console	Х	X
View the History file	Х	Х
View all events	Х	Х
Trigger manual refreshes	Х	Х
View the Status Panel {System displayed, System	Х	Х
Click CST logo for software information	Х	Х
Add/edit event comments		Х
Create service events	Х	Х
Create and save entries in the Admin dialog box		Х
Edit Custom Information		Х
Edit Event Reason		Х

TABLE 4-1 Abilities of Sun Configuration and Service Tracker Access Levels

Note – If a user is not added to cstadm or cstops, the user cannot log in to Sun Configuration and Service Tracker. An error message, "ERROR: not authorized to access CST" displays in the login session.

Site Registration

Sun Configuration and Service Tracker 3.6.0 has a built-in feature to send all collected Sun Configuration and Service Tracker data to a secure database in Sun. The benefit of sending the data to Sun is to enable generation of detailed availability and configuration reports using the data collected. The reports are enriched by the use of normalized data from multiple customer sites and can provide insight into the overall availability of systems in the enterprise. These reports can be obtained with the help and interaction of your local Sun representative. For more details about the benefits of this registration, contact your local Sun representative.

Before this feature can be enabled, you must register the site with Sun and enable data flow from the Sun Configuration and Service Tracker server to Sun. The registration process is completed using the *Site Info Dialog*.

There are three tabs within the Site Info Dialog window: Customer Contact Info, Sun Contact Info, and Registration Info. All three must be completed to configure your environment. For details about entering your site information into these tabs, see "Site Info Dialog" on page 3-8.

	Site Info Dialo			
	Java Applet V	Vindow		
Customer Contact Info	Sun Contact Info	Sun Contact Info Registration Info		
Company Name : Business Unit : Ticker Symbol : Street Address : City : State : Country : Zip/Postal Code : Customer Contact				
System Admin Contact	Alte	rnate Customer Contac	t	
Name :	Na Ph	me : one # : ger # : ail ID :		
Data Transfer Transmission of Data to Registration Status: Unr Transport Mode: None	Sun Microsystems, egistered Apply	Inc.: Disabled Close		

FIGURE 4-1 Site Registration, Customer Contact Information tab

Prepare for Registration

You must set up the environment to prepare for registration. The server must have the ability to send email to the outside world.

Registration Prerequisites

Ensure that the following steps have been completed before starting the registration process.

1. Ensure that all fields in the Customer Contact Info and Sun Contact Info tabs of the Site Info Dialog window are completely and accurately completed.

Note – The alternate contact information is not mandatory.

2. Ensure the system administrator's contact email address is correctly entered in the appropriate field.

Since the registration key will be sent to the system administrator's contact email address, this information must be correct. If the contact email address is incorrect, the key will be lost.

Site Info Dialog	Site Info Dialog				
Java Applet Window	Java Applet Window				
Customer Contact Info Sun Contact Info Registration Info	Customer Contact Info Sun Contact Info Registration Info				
Primary Sun Contact Name : Phone # : Pager # : Email ID : Secondary Sun Contact Name : Phone # : Phone # : Pager # :	Request Key Service Selection • SunUp Other I Accept the terms of the agreement View Agreement Auto register using CST local email account?				
Email ID : Apply Close	Registration complete Image: Complete Registration Successful. Please restart the CST GUI for changes to take effect on the UI. OK OK Register Key Customer ID : SUNW O75C-E122-8BEE-7C7D Register Close				

FIGURE 4-2 Site Registration - Sun Contact Information & Registration Information tabs

3. Read the entire agreement and be sure you understand it.

If you have questions, please contact your local Sun representative.

4. After reading the agreement, check the AGREE TO THE AGREEMENT box.

If setting up an account for Sun Configuration and Service Tracker in the middleware server is acceptable, Sun Configuration and Service Tracker will set up an account and use it as sender to transmit the data from that account. It can also receive email coming in and can be used in future to provide automated reporting and other services.

5. If setting up a Sun Configuration and Service Tracker account in the middleware server is acceptable, check the **SETUP CST ACCOUNT** box. (This is optional.)

To Obtain a Registration Key

When a site submission is successful (if all mandatory data fields are completed), an email is sent to the Sun representative identified in the Sun Contact Info tab that includes all the data entered in the Admin dialog box.

The Sun representative confirms that the installation is adequately set up to send data to Sun and that all the mandatory fields have appropriate information. Once confirmed, the Sun representative forwards the email to Sun for a registration key and a customer ID. When granted, the registration key and customer ID are forwarded by email to the address given in system administrator contact email address.

- 1. Access this information and enter them in the Register Key panel in the *Registration Info* tab of the *Site Info Dialog*.
- 2. Click the **REGISTER** button.

Registration Completion

If the registration is successful, a Sun Configuration and Service Tracker Registered event is created on each of the agents currently reporting into this midddleware server. The Sun Configuration and Service Tracker Registered event, configuration files, and the user data fields for these agents are sent to Sun. On the Admin dialog box, under Customer Contact Info, Transfer Data to Sun is set to ENABLED. If setting up a Sun Configuration and Service Tracker account is selected, a Sun Configuration and Service Tracker account is created on the server.

Network Protocols

To Set Network Transport Between Agent and Server

Sun Configuration and Service Tracker support for TCP protocol between the Sun Configuration and Service Tracker agent and server is introduced with Sun Configuration and Service Tracker 3.6.0. The network transport between the Sun Configuration and Service Tracker agent and the Sun Configuration and Service Tracker server can be either TCP or UDP (RPC). If you want to use TCP protocol, you must specify your selection when the Sun Configuration and Service Tracker agent is first attached to the server. See Chapter 5, "Sun Configuration and Service Tracker Utilities," for more information.

The default network transport between the Sun Configuration and Service Tracker agent and the Sun Configuration and Service Tracker server is UDP (RPC). This protocol is a full-duplex protocol where the Sun Configuration and Service Tracker agent issues RPC to the Sun Configuration and Service Tracker server and vice versa.

If the selected transport protocol is TCP, the Sun Configuration and Service Tracker server and agents listen on TCP port 3742. You must open port 3742 through the firewall for any traffic to pass in both directions.

If the selected transport protocol is UDP, the RPC program number used by Sun Configuration and Service Tracker is 805306372 (30000004 hex). By default, the system assigns a random port as the UDP port; however, the user can overwrite the random port assignment by setting a range of ports to which the Sun Configuration and Service Tracker process binds. In order to do this, there is a file on both the agent and the server that must be edited:

/var/opt/SUNWcst/files/port_cfg

To Override the Random Port Assignment

1. Check the port_cfg file for the following two lines. Add these two lines if they are not currently in the file.:

minport=<a minimum port number>
maxport=<a maximum port number>

- 2. Each user must restart the Sun Configuration and Service Tracker process for the port range to take effect by completing the following steps:
 - a. Stop and restart Sun Configuration and Service Tracker by following these steps. At a root prompt, type:
 - # /etc/init.d/cst stop
 - # /etc/init.d/cst start

To Force the Sun Configuration and Service Tracker Agent to Use TCP

In case of an upgrade from an earlier version of Sun Configuration and Service Tracker to Sun Configuration and Service Tracker 3.6.0, the transport protocol used will be UDP. To force the Sun Configuration and Service Tracker agent to use TCP as the network transport protocol complete the following steps:

1. Stop the Sun Configuration and Service Tracker agent. Type:

```
# /opt/SUNWcstv/sbin/cstadm stop
```

2. Edit the file, /var/opt/SUNWcst/xprt, with this command:

XPRT_MODE<tab>TCP

3. Restart the Sun Configuration and Service Tracker agent. Type:

```
# /opt/SUNWcstv/sbin/cstadm start
```

After you successfully execute these steps, the Sun Configuration and Service Tracker agent and server automatically negotiate to use TCP as the transport protocol.

To Set Network Transport Between Server and Client

The network transport between the Sun Configuration and Service Tracker server and the Sun Configuration and Service Tracker client is TCP. By default, a random port is assigned by the system, The user can overwrite it by setting a range of ports for the Sun Configuration and Service Tracker server to bind to. To override the default, edit the file:

/var/opt/SUNWcst/files/port_cfg

1. Check the port_cfg file for the following two lines. Add these two lines if they are not currently in the file.:

tcpminport=<a minimum port number> tcpmaxport=<a maximum port number>

Note – You must restart the Sun Configuration and Service Tracker server for the port range to take effect.

- 2. Type the following commands to stop and restart Sun Configuration and Service Tracker:
 - # /etc/init.d/cst stop
 - # /etc/init.d/cst start

Tuning Sun Configuration and Service Tracker Trigger Intervals

Sun Configuration and Service Tracker automatically decides if a resource is present and when detected, assigns the default tracking interval and invokes the tracking thread for that detected resource. The tracking thread includes detection of dynamic reconfiguration of hardware change and cluster configuration changes. The defaults are preset to keep the load on the system light and still be frequent enough to detect most, if not all, events.

The tracking intervals are tunable to better suit specific system needs. The tuning is achieved by:

- 1. Manually editing the cst.conf file in the /var/opt/SUNWcst directory of each system.
- 2. Restarting Sun Configuration and Service Tracker by issuing a CST STOP followed by a CST START.

Note – See the syntax to edit the file and restarting in section "Tune Sun Configuration and Service Tracker Event Detectors" on page 4-12.

The following table indicates the various entries that control the tracking intervals and their limits. The value must be within the stated limits. Values outside of these limits are automatically reset to the minimum or maximum value.

		Value		
Tracking Entity	Parameter	Min	Мах	
Dynamic Reconfiguration (DR) Thread	DR_INTERVAL	3600	86400	
Field Replaceable Unit (FRU) Changes	FRUINFO_ENABLE	0	1	
Volume Manager (VM) Changes	VXVM_INTERVAL	900	86400	
Sun Fire 15K FRU Changes	SF15K_FRU_INTERVAL	900	86400	
Sun Fire 15K Events	SF15K_EVENT_INTERVAL	1800	86400	
*Fru probe on SunFire 3800, 4800, 4810, 6800	SUNFIRE_FRU_PROBE_DISABLE	0	1	
*COD probe on SunFire 3800, 4800, 4810, 6800	SUNFIRE_COD_PROBE_DISABLE	0	1	
Cluster Thread	CLUSTER_INTERVAL	50	86400	

 TABLE 4-2
 Tracking Intervals

*These two entries apply to only the listed server platforms.

Tune Sun Configuration and Service Tracker Event Detectors

Some of the event detectors use polling to check for changes. The monitoring frequency of those event detectors can be tuned through the cst.conf file in /var/opt/SUNWcst directory. The format adopted in this file is:

<event detector_interval><tab><value>

```
Note – The field separator is <tab>.
```

For all parameters ending with _INTERVAL, the value indicates the monitoring interval in seconds. Each monitoring entity has a pre-specified maximum, minimum, and a default period. The Sun Configuration and Service Tracker process resets any setting above the maximum or below the minimum to the maximum or minimum periods respectively. The default setting is the one set when Sun Configuration and Service Tracker is installed. A preset value of 0 indicates that the monitoring of that entity has been stopped.

FRUINFO_ENABLE is a binary parameter.

If FRUINFO_ENABLE is set to 1, collection of FRU information is enabled. Otherwise it is disabled. The default value of this parameter is 1.

The following is a sample cst.conf file:

```
# CST Configuration File.
# REVISION: 3.0
# Format:
#
        <Key Name><tab><value>
#
#
DR INTERVAL
                3600
VXVM INTERVAL
                900
FRUINFO ENABLE 1
CLUSTER INTERVAL
                         300
SF15K_FRU_INTERVAL
                         1800
SF15K EVENT INTERVAL
                         3600
```

To change a monitoring interval for a specific entity, the value parameter for that entity must be manually edited in the cst.conf file.

Note – The change does not take effect until the cst daemon is restarted.

To stop and restart the CST daemon use the following commands:

The CST Stop command:

/etc/init.d/cst stop

The CST Start command:

/etc/init.d/cst start

Sun Configuration and Service Tracker Detach

Caution – While an agent is detached from its Sun Configuration and Service Tracker server, the agent stores the data which is normally transferred to the Sun Configuration and Service Tracker server and stored in the repository. If a crash occurs before the agent is reattached and the data is transferred to the server, the data is lost.

To Detach Sun Configuration and Service Tracker from Middleware Server

1. Create an app_event in the agent with event name CST detached; type:

\$ /opt/SUNWcstv/bin/app_event "CST detach" "CST
detached from <middleware_name>"

2. Stop Sun Configuration and Service Tracker; type:

\$ /etc/init.d/cst stop

- 3. Edit the /var/opt/SUNWcst/cst.pref file and remove the value for MIDDLEWARE field.
- 4. If Sun Configuration and Service Tracker is to run in a stand-alone mode (without reporting to any middleware), restart Sun Configuration and Service Tracker; type:
 - \$ /etc/init.d/cst start

Sun Configuration and Service Tracker Tracking During OS Upgrades

Ensure that a copy of Sun Configuration and Service Tracker is running on the systems at all times.

After an OS upgrade on the agent, if the Sun Configuration and Service Tracker data on the agent is lost, the agent must be restored from the copy on the middleware.

To Restore A Copy of Sun Configuration and Service Tracker

- 1. Copy all the agent files under the agent hierarchy in the middleware repository to the /var/opt/SUNWcst directory on the agent host.
- 2. Run the pkgadd command for the agent package on the agent system.

For the System Service Processors (SSP) and System Controllers (SC) on multidomain systems, the restore also involves restoring the platform data in addition to the agent data. The platform data under the platform hierarchy must be copied to:

SSP: /var/opt/SUNWcst/ssp for an E10K SSP

SC /var/opt/SUNWcst/ssc for a Sun Fire 15K SC

To determine the location of the platform data, consult the guidelines in "To Attach a Multi-domain Agent to Sun Configuration and Service Tracker Server" on page 2-23.

Note – Sun Configuration and Service Tracker is not automatically installed as part of an OS upgrade. It must be installed after the OS upgrade.

While installing Sun Configuration and Service Tracker, remember that the Sun Configuration and Service Tracker software is only 'fresh installed' the first time. A fresh installation of Sun Configuration and Service Tracker software

means that no Sun Configuration and Service Tracker files or data have ever existed on the agent system nor on its middleware repository. In this manual, this is referred to as a new installation.



Caution – After an operating system (OS) upgrade, the local data on the agent system might be erased, but a copy is still maintained on the middleware system to which the agent was previously *attached*. After an OS upgrade, you must restore the Sun Configuration and Service Tracker agent data manually from the middleware repository. Only after that data restoration should you install the agent package. Performing these steps in any other sequence can cause data inconsistencies between the local agent data and the agent data on the middleware system.

Managing Hierarchy

Sun Configuration and Service Tracker provides you with the functionality to group your monitored systems for ease of viewing a specific system or a group of systems. By configuring the hierarchy of your monitored nodes in groups, you can browse through the top level group names and drill-down as required. Using the Hierarchy functionality can also help with UI loading performance.

You may want to change the Sun Configuration and Service Tracker hierarchy configuration if you regroup your monitored systems. Upgrading your Sun Configuration and Service Tracker version does not alter the hierarchy. When you want to change the hierarchy of your Sun Configuration and Service Tracker monitored systems, perform the steps in the following section.



Caution – The procedure of moving hierarchy using the utility, cstattach, is now obsolete because of the possible impact to causecode data at the Sun database and, in some cases, on site causecode data.

Move Agent Data to a Different Hierarchy

Sun Configuration and Service Tracker events are collected on the agent and forwarded to the Sun Configuration and Service Tracker server, middleware, and stored in the server repository. Each monitored agent machine includes a file, cst.pref, where the hierarchy settings are read when events are to be sent to
the repository. A copy of that file resides on the middleware under the repository. The location where the agent events are stored in the repository on the middleware must be created so, when the location is read in the cst.pref file, the data can be sent correctly.

These steps include backing up the event data for the agent system being moved and establishing all of the correct links within this structure. The following steps explain how to alter the hierarchy for an agent and move the agent data.

To Alter the Hierarchy for an Agent

1. Back up the agent data that resides under the server repository.

The server repository is located on the Sun Configuration and Service Tracker middleware server.

2. Before you proceed, check that there is no /var/opt/SUNWcst/bkup_events file on the agent system.

If this file exists, it means the agent is still trying to send the backlogged events to the server. Make sure that the middleware server is up and running and wait until bkup_events is no longer present.

3. Log in to the agent system as superuser.

Note – All of these commands are to be run as superuser.

4. Stop the CST daemon on the agent system; at the root prompt on the agent machine type:

```
/opt/SUNWcstv/sbin/cstadm stop
```

5. Log in to the middleware server system as superuser and perform hierarchy moving; run these commands at the root prompt:

```
cat /var/opt/SUNWcst/cst.pref | grep ROOT_PATH
```

```
cd <ROOT_PATH value in cst.pref>
```

These commands find the location of the repository and the cst.pref file on the Sun Configuration and Service Tracker server.

6. Locate the agent hierarchy and create a directory in the new location to hold agent data.

7. After you create the new location, move the hierarchy to the new place inside the ROOT_PATH using the mv command.

In this step you create the new location on the middleware under the repository where the agent data will be stored, and you move the existing data for the agent into the new location.

Execute the commands on the middleware at a root prompt as superuser.

```
Example:
Moving a/b/Agent1.Sun.COM to b/c/Agent1.Sun.COM
# mkdir -p b/c
# mv a/b/Agent1.Sun.COM b/c
```

- 8. On the middleware server, manually edit the cst.pref file to update the HIERARCHY value. The new value must reflect the directory created in the step 7. (For example, b/c/Agent1.Sun.COM/cst.pref)
- 9. On the agent system, manually edit the cst.pref file to update the HIERARCHY value. The location of this file is: /var/opt/SUNWcst/cst.pref
- 10. Make sure that the HIERARCHY values in both copies of the cst.pref files modified in steps 8 and 9 are identical.

Note – The HIERARCHY in cst.pref is a relative path to ROOT_PATH where agent data is stored. This value should also include the proper agent directory name (case sensitive) that is the agent hostname at the end. Preserve <tab> key, which is the separator between HIERARCHY and hierarchy value. For example HIERARCHY<tab>a/b/agent1.company.com

11. Start the Sun Configuration and Service Tracker agent daemon; at the root prompt on the agent machine, type:

/opt/SUNWcstv/sbin/cstadm start

Service and Cause Code Updates

SERVICE EVENT and **UPDATE CAUSE CODE** buttons are provided in the CST History tab of the main CST UI console. Service events are used by the service engineers while the system is under maintenance, whereas the Update Cause Code button is used while updating the cause code for the Sun Configuration and Service Tracker history events.

Cause Codes

- Every event from each of the systems being monitored can and should be annotated with a reason. Click the Cause button and use the Event Cause Code Dialog box as a structured approach for assigning the reason. This is useful for identifying the major and common causes, but its ability to provide details is limited. More meaningful explanations should be provided where appropriate, by using the free-format Comments section. This information can be very useful during periodic discussions, on the availability and other statistics on the systems in the enterprise.
- When marking the event cause for an outage, assign the Planned/Unplanned flag to the Shutdown event and not the Reboot event.
- Every action performed on the system (other than those automatically detected) should be captured using the Create Service Event feature. It is not necessary to give every action a separate Create Service Event, since the comments can be appended in a single event. However, in order to keep the action timestamps correct, it is important that the actions after a reboot appear in a service event after the reboot.
- All actions that took place between a Shutdown and a Reboot should be captured as Comments for the Reboot event.
- Service performed while the system is online should be captured through a separate Service Event. A single Service event between a Reboot and a subsequent Shutdown can be used to capture all events during that period.
- Report any events that should have been detected, but were not, to your service provider.

Service and Cause Code Updates

Chapter 5

Sun Configuration and Service Tracker Utilities

Several command-line utilities are included in the SUNWcstu package. These utilities are used to perform various administrative functions. Executing these utilities require root level access to the system where the packages are installed.

The following lists each of these utilities:

- "cstattach" on page 5-2
- "cstattagt" on page 5-6
- "cstfind" on page 5-8
- "findevent" on page 5-12
- "cstlshost" on page 5-17
- "setcause" on page 5-21
- "app_event" on page 5-25
- "addsunfire" on page 5-29
- "cstdecomm" on page 5-32

cstattach

Name

cstattach - binds a Sun Configuration and Service Tracker agent to a Sun Configuration and Service Tracker middleware system.

Description

This utility is part of the Sun Configuration and Service Tracker server installation and is to be run on the Sun Configuration and Service Tracker server system. The default location is:

/opt/SUNWcstv/bin

cstattach can be used to attach Sun Configuration and Service Tracker 3.6.0 agents that are installed and running in an unattached mode. The protocol to be used between the agent and the server can also be specified.

By attaching an agent to a Sun Configuration and Service Tracker server system, you can:

- View the Sun Configuration and Service Tracker agent data through Sun Configuration and Service Tracker GUI. The data includes system events, system configuration, and system availability data.
- Annotate an outage event cause code using GUI or command line interface.
- For SunUP customers, it is recommended that you do cstattach for unattached agents as soon as you can. This enables customer benefits from the SunUPTM program for attached agents.

Supported Platforms

cstattach is supported on Solaris 2.6, 2.7, 8, 9 and 10. It is designed to work with Sun Configuration and Service Tracker 3.6.0.

Checklist

Before you use cstattach, please check the following:

- 1. The agent being attached must be up and running when the attachment process is performed. Ensure that there is no scheduled downtime for the agent around the time you want to use this command. cstattach usually takes around 30 seconds per agent.
- 2. The middleware Sun Configuration and Service Tracker daemons performing attach process (cstd.svr and csthb.svr) must be up and running.

Note – When working with versions of Sun Configuration and Service Tracker prior to Sun Configuration and Service Tracker 3.5.2, the Sun Configuration and Service Tracker daemon names are cstd and csthb.

3. Make sure that the agent version is Sun Configuration and Service Tracker1.5.1 or later.

Note – Older versions of Sun Configuration and Service Tracker do not support the TCP protocol. To use the TCP protocol between the agent and the server, both must be running Sun Configuration and Service Tracker 3.6.0. For details on the TCP/UDP protocols, see "Network Protocols" on page 4-9.

- 4. For a large number of monitored systems, it is recommended that the hierarchy tree is planned ahead to eliminate mistakes that may require moving an agent from one hierarchy to another. (hierarchy is optional) For steps to relocate a Sun Configuration and Service Tracker agent node to another hierarchy, see "Move Agent Data to a Different Hierarchy" on page 4-16.
- 5. Collect the agent key from each agent. The agent key is the value inside /var/opt/SUNWcst/akey for each monitored agent.

Usage

```
cstattach [-h hierarchy] -a <agentname> -k <agentkey>
[-t transport][-m middleware]
```

- The hierarchy parameter is optional. It is used to organize the monitored systems into different groups (hierarchy names). In the case that you have many agent systems, specifying hierarchy will also help in GUI loading performance.
- The transport parameter is the IP protocol to be used between the agent and the server and is optional. Valid values are: TCP and UDP. The default protocol is UDP; UDP is used when no transport parameter is manually set.

Note – Hierarchy must be a relative path under middleware repository where the agent directory and its data are maintained.

- Example: department1/group2
- agentname is the agent name to attach.
- agentkey can be obtained from /var/opt/SUNWcst/akey on each agent machine.
- middleware parameter is optional, but is required if Sun Configuration and Service Tracker agent and Sun Configuration and Service Tracker middleware are located in different Internet domains. The specified middleware name must be a fully qualified hostname that can be resolved on the agent.

Examples

Example 1

Assuming the middleware hostname is *cstserver* running in eng.sun.com domain. The agent name being attached is cstnode1.eng.sun.com.

The agent key (/var/opt/SUNWcst/akey) on cstnode1 machine is 123456.

The following attach command can be used:

cstattach -a cstnode1.eng.sun.com -k 123456

This puts the agent data in:

```
[repository_path]/cstnode1.eng.sun.com
```

Example 2

Same as Example 1 with hierarchy path specified.

```
# cstattach -h department1/group2 -a
cstnode1.eng.sun.com -k 123456
```

This puts the agent data in:

```
[repository_path]/department1/group2/
cstnode1.eng.sun.com
```

Example 3

Same as Example 1 except that the agent is located in different domain germany.sun.com.

```
# cstattach -h europe/germany -a
cstnode2.germany.sun.com -k 123456 -m
cstserver.eng.sun.com
```

This locates the agent data in:

```
[repository_path]/europe/germany/cstnode2.germany.
sun.com
```

Note – The [repository_path] is the location specified during middleware installation. This value is also stored under ROOT_PATH key in /var/opt/SUNWcst/cst.pref on the Sun Configuration and Service Tracker middleware system.

Example 4

Same as Example 1 except this example enables TCP transport between the Sun Configuration and Service Tracker server and the Sun Configuration and Service Tracker agent:

cstattach -a cstnode1.eng.sun.com -k 123456 -t TCP

Note – If you do not use the default protocol UDP, use this command to set up the full duplex TCP communication between the Sun Configuration and Service Tracker server and the agent. The -t setting is permanent, and applies to all communications after the attach operation has been completed. For information on Sun Configuration and Service Tracker 3.6.0 support for TCP and UDP, see "To Set Network Transport Between Agent and Server" on page 4-9.

See also the section on the cstattagt utility.

cstattagt

Name

cstattagt - binds a Sun Configuration and Service Tracker agent to a Sun Configuration and Service Tracker middleware system

Description

This utility provides similar functionality to the cstattach utility. The differences between this utility and cstattach are:

- cstattagt is present and is to be run on Sun Configuration and Service Tracker agent and not from the middleware server.
- No agent key is required for the attach operation.
- The transport protocol to be used between the agent and the server can be specified as either TCP or UDP. The default protocol is UDP. The RPC/UDP traffic is only initiated from Sun Configuration and Service Tracker agent to the middleware server (uni-directional) which may be useful for strict firewall setting.
- cstattagt provides no options for customizing the agent nodename. The agent nodename which displays under the agent hierarchy on middleware server is the hostname of the agent (as appeared in hostname unix command).

 cstattach provides more flexibility than cstattagt in this regard where agent hostname can be explicitly defined either by using fully qualified name or by short hostname.

Supported Platforms

cstattagt is supported on Solaris 2.6, 7, 8, 9 and 10.

Checklist

Before you use cstattagt, please check the following:

- 1. The Sun Configuration and Service Tracker agent being attached must be up and running. It can take from a few seconds to 2 minutes for the attach procedure to complete.
- 2. The middleware that the agent will attach to must be up and running.
- 3. To attach Sun Configuration and Service Tracker 3.6.0 agent, the middleware server must be running Sun Configuration and Service Tracker version 3.0 or later.
- 4. For a large number of monitored systems, it is recommended that the hierarchy tree is planned ahead to eliminate mistakes that may require moving an agent from one hierarchy to another.

For details on how to relocate a Sun Configuration and Service Tracker agent data from one hierarchy to another hierarchy, see "Move Agent Data to a Different Hierarchy" on page 4-16.

Usage

cstattagt [-h hierarchy] [-t transport] <middleware>

Middleware is the middleware hostname to which the agent attaches.

Transport is the transport layer protocol to use. You can select between TCP and UDP. UDP is the default.

Hierarchy is the relative path under middleware repository where the agent directory and its data are maintained.

This parameter is optional. If you have many Sun Configuration and Service Tracker agent systems, it is recommended that the hierarchy is used to organize the monitored systems and to improve UI loading performance.

Example: department1/group2

Example 1

Attach an agent to cstserver.eng.sun.com

cstattagt cstserver.eng.sun.com

Example 2

Attach an agent with hierarchy defined and specifying TCP protocol:

```
cstattagt -h europe/uk/eng -t TCP cstserver.eng.sun.com
```

```
This puts the agent in: [cstserver_repository_path]/europe/uk/eng/agenthostname
```

SEE ALSO

"cstattach" on page 5-2.

cstfind

Name

cstfind - To find nodes with matching patterns.

Synopsis

cstfind [-o outputfile]

```
cstfind [ -s key=value ] [ -h pattern ] [ -p package ] [-x patch \# ]
```

```
-i inputfile ] [ -o outputfile ]
```

Description

The cstfind utility searches for a pattern in the *probe.current* file under each input directory node and returns the list of matching directory nodes.

cstfind should be run only on a machine running Sun Configuration and Service Tracker server.

Options

The following options are supported for cstfind:

TABLE 5-1 CSt	find Options
---------------	--------------

Option	Description	
-s key=value	Specify a key and value to be searched under the "System Information" section of the probe current file. For details refer to the examples given at the end of this section	
	If the value specified starts with an exclamation mark (!), the nodes returned by cstfind are the ones which do not match the value pattern.	
-h hardwareinfo	Specify a hardware type to be searched under the "Installed Hardware" section of the probe.current file. For details refer to the examples given at the end of this section. If the hardwareinfo that is specified starts with an exclamation mark (!), the nodes returned by cstfind are the ones which do not match the hardwareinfo pattern.	
-p pkgname	Specify a software package to be searched under the "Software Package(s)" section of the probe.current file.	
	For details refer to the examples given at the end of this section. If the specified pkgname pattern starts with an exclamation mark (!), the nodes returned by cstfind are the ones which do not match with the pkgname pattern.	

Option	Description
-x patch #	Specify a patch number to be searched under the "Software Patch(es)" section of the probe.current file. For details refer to the examples given at the end of this section. If the specified 'patchnum' pattern starts with n exclamation mark (!), the nodes returned by cstfind are the ones which do not match with the 'pkgname' pattern.
-i inputfile	Specify an input file, which contains a list of directory nodes. The "probe.current" file under the specified nodes will be searched for the matching pattern. The inputfile should contain the directory path under which the "probe.current" is residing.
	If -i option is not specified and if the system is used as a Sun Configuration and Service Tracker Server, cstfind searches for the pattern in every "probe.current" file under ROOT_PATH. The variable ROOT_PATH is read from /var/opt/SUNWcst/cst.pref file.
	For details refer to the examples given at the end of this section.
-o outputfile	Specify an output file, where the list of directory nodes whose "probe.current" matches with the specified pattern will be stored.
	If the $-o$ option is not specified the output will be defaulted to stdout.
	For details refer to the examples given at the end of this section.
	A combination of -s, -h, -p & x will be supported by this utility. Multiple usage of the same option is allowed. Please look at the examples given in the next section for further details.

TABLE 5-1cstfind Options

Examples

Example 1

To list all the agent nodes configured under this Sun Configuration and Service Tracker server.

```
example% cstfind -o inputfile
```

The list of nodes will be captured in the file 'inputfile'. We use this file in our later examples.

Example 2

To list all the nodes with OS version Solaris 2.8.

example% cstfind -s os=2.8 -i inputfile -o outputfile

The file inputfile should contain all the directory nodes under which the search has to be done. The outputfile will be created with contents as list of nodes matching OS version "2.8" under "System Information" section of the probe.current file.

Example 3

To list all the nodes without a patch number ABCD1234.

example% cstfind -x !ABCD1234 -i inputfile

Since the -o option is not specified, the list is printed on stdout.

Example 4

To list all the nodes with number of CPUs equal to 12 and with CPU, type: sparc.

example% cstfind -s cpu=12 -s cpu=sparc -i inputfile

Exit Status

The following exit values are returned:

TABLE 5-2Exit Values

Value	Definition
0	All nodes were traversed successfully
1	An error occurred.

Note – cstfind uses a case insensitive search algorithm.

findevent

Name

findevent - CST Event finder

Description

findevent scans all the nodes in the middleware repository or in the specified hierarchy for the events that are of user-interest. User can specify the criteria of the search including:

TABLE 5-3	findevent	search	criteria	choices	

Criteria	Rules
event type(s)	(hardware change, reboot,)
period	(last month, since inception,)
weekday(s)	(mon, tue, wed, thu, fri, sat, sun)
time	(day time period i.e. from 8am to 5pm)

It is also possible for user to define multiple rules by creating rule file.

Rule file is useful for advanced event filtering. findevent also supports "extend" format which can be used as the input to other Sun Configuration and Service Tracker utilities i.e. setcause to globally set cause code for shutdown events that match period, weekdays and time specified. Running this program as root is recommended as this guarantees that the Sun Configuration and Service Tracker history files and cause code files can be accessed.

Supported Platforms

findevent is supported on Solaris 2.6, 7, 8, 9, and 10. It should work with all existing Sun Configuration and Service Tracker versions including Sun Configuration and Service Tracker1.5_AMS, Sun Configuration and Service Tracker2.1_AMS, Sun Configuration and Service Tracker2.1_AMS, Sun Configuration and Service Tracker2.1U1_AMS.

Usage

Usage: ./findevent [-p PERIOD] [-w WEEKDAY(S)] [-t TIMESTART TIMEEND] [-h HIERARCHY] [-n NODENAME] [-f FORMAT] [-r RULEFILE] [-c] EVENT_TYPE(S) -l USER_COMMENT_LENGTH

EVENT_TYPE (Default is "any")

EVENT_TYPE can be one or more of the following types:

This field is the only mandatory field. More than one event_type can be specified by separating them with space. The allboot event_type prints all boot-related events.

. –	
hardware	hardware change events
software	software change events
shutdown	system shutdown events
panic	system panic events
reboot	system reboot events
sysavail	system available events
allboot	shutdown panic reboot sysavail events
service	service events
domain	e10k domain change events
boardpwr	e10k board power on/off events
syscfgchange	e10k system configuration change events
cstpkgadd	Sun Configuration and Service Tracker package upgrade events

TABLE 5-4Event Types

cstpkgrm	Sun Configuration and Service Tracker package remove events
cststart	Sun Configuration and Service Tracker manually start events
cststop	Sun Configuration and Service Tracker manually stop events
cstinception	Sun Configuration and Service Tracker inception event
custominfo	customer info update events
other	other events
any	any events

TABLE 5-4Event Types

PERIOD

PERIOD can be one of the following (Default is since INCEPTION):

- LAST24HRS
- THISWK
- LASTWK
- THISMTH
- LASTMTH
- THISQT
- LASTQT
- THISYR
- LASTYR
- INCEPTION
- CUSTOM start_date end_date

start_date and end_date format: mm/dd/yyyy

WEEKDAY

WEEKDAY can be one or more of the following (Default is any day):

- MON
- TUE
- WED
- THU

- FRI
- SAT
- SUN

Two or more days can be specified with comma separation and without spaces.

Ex. -weekday SAT,SUN means searching for Saturday and Sunday

TIMESTART and TIMEEND

TIMESTART and TIMEEND is in 24-hour time format hh:mm:ss

Default behavior will search for any day time

FORMAT

FORMAT can be one of the following (Default is txt):

 TABLE 5-5
 Format Options

txt	plain text output
extend	this format print event number and planned/unplanned value

The extend format is also used as an input to setcause utility

HIERARCHY

HIERARCHY is the relative hierarchy path under Sun Configuration and Service Tracker middleware repository Searching is applied only for the agents in the specified hierarchy.

Default: the program scans for all hierarchies

RULEFILE

RULEFILE is useful when more than one set of rules is needed.

For example, if user wants to find events that happen during non-business hours (assuming 6pm - 8am mon-fri, all day sat-sun), user can create a rule file with the following content:

MON,TUE,WED,THU,FRI 00:00:00 08:00:00 MON,TUE,WED,THU,FRI 18:00:00 23:59:59 SAT,SUN 00:00:00 23:59:59

- Rule file can only contain weekday and time period.
- The parameters -w and -t are ignored if rule file is specified.
- See also: setcause utility which accepts findevent input to set cause code (planned/unplanned) for non-prime time hours.

Option

Option -c indicates that the cause code text is also printed.

Note - The *findevent* utility can also import the node list from cstfind utility.

User can specify -i INPUTFILE option where INPUTFILE is the output from cstfind utility.

Usage Examples

• Find any events that happened during this week; type this command:

```
# findevent -p THISWK any
```

• Find any PANIC, Shutdown, Reboot events that happened during this week; type this command:

```
# findevent -p THISWK allboot
```

• Find any PANIC, Shutdown, Reboot events that happened on Mon-Fri from 8am to 5pm since INCEPTION; type this command:

```
# findevent -w MON,TUE,WED,THU,FRI -t 08:00:00
17:00:00 allboot
```

• Find all machine names that newly deploys Sun Configuration and Service Tracker this year and let the user comment go up to 200 characters; type this command:

```
# findevent -p THISYR cstinception |grep -v " "| cut
-d ":" -f 1 -l 200
```

 Find software upgrades including Sun Configuration and Service Tracker software upgrade during the weekend and during this year; type this command:

findevent -p THISYR cstinception

- Find any events generated by app_event utility (Not match any category)
 - # findevent other

cstlshost

Name

cstlshost - To list the selected fields of system information.

Synopsis

cstlshost [-f field name] [-i inputfile] [-o outputfile]

Description

The cstlshost utility retrieves the field information specified by -f option from system information of the probe.current file under all nodes or a set of nodes specified in the file by -i option and outputs the result to either standard output or to file specified by -o option.

cstlshost should be run only on a machine running Sun Configuration and Service Tracker server.

Options

The following options are supported for cstlshost:

-f field name

Specify a field name to be retrieved from the system information section of the probe.current file. The valid field names are:

- System Model
- Kernel Architecture
- OS Type
- Host Name
- Host Aliases
- Host Address(es)
- Host ID
- Serial Number
- Main Memory
- Total Disk Space
- Total Disks
- Total Cdroms
- ROM Type
- Number of CPUs
- CPU Type
- Timezone
- Boot Time
- MAC Address
- HIERARCHY

For details refer to the examples given at the end of this section

-i inputfile

Specify an input file, which contains a list of directory nodes. The probe.current file under the specified nodes is searched to retrieve the fields. The input file should contain the directory path under which the probe.current file resides.

For details, refer to the examples given at the end of this section.

-o outputfile

Specify an output file, where the retrieved field information is stored.

If the -o option is not specified, the output is defaulted to stdout. For details, refer to the examples given at the end of this section.

Note – Multiple usage of the option -f is allowed. Please look at the examples given in the next section for further details.

Examples

Example 1

To list system information like host name, host id of all the nodes configured under this Sun Configuration and Service Tracker server.

example% cstlshost -f "Host Name" -f "Host ID"

TABLE 5-6Example 1 Output

Host Name	Host ID
Diag1	80f69438
Diag2	80342e20

Example 2

To list host name, serial number, system model, total disks, and hierarchy of all the nodes and output to a file.

```
example% cstlshost -f "Host Name" -f "Serial Number"
-f "System Model" -f "Total Disks" -f "HIERARCHY" -o
outputfile
```

The resulting outputfile contains:

Host Name	Serial e Number System Model		Total Disks	Hierarchy
Diag1	2159449448	Ultra 60 UPA/PCI (2 X UltraSPARC II 450MHz)	1	NULL
Diag2	2155097632	SPARCserver 1000	13	a/b/c/d

In the output of cstlshost, each field in a record is separated by the tab character. To get more aligned and formatted output, use the cstprint utility.

Example 3

To list hostname, mac address, and IP address for a set of nodes specified in the input file.

```
example% cstlshost -f "Host Name" -f "MAC Address" -
f "Host Address(es)" -i inputfile
```

 TABLE 5-8
 Example 3 Output

Host Name	MAC Address	Host Address(es)
TestSys1	8:0:20:b8:95:68	129.16.203.14
TestSys2	8:0:20:67:2e:20	132.29.88.33

Since the -o option is not specified, the list is printed out on stdout.

Exit Status

The following exit values are returned:

TABLE 5-9	Exit Values
Value	Description
0	All nodes were traversed successfully
1	An error occurred

The cstlshost utility uses case sensitive, full field names to list.

setcause

Name

setcause - apply event reasons to Sun Configuration and Service Tracker outage events

Synopsis

setcause utility can be used to apply outage reasons (cause code) to certain outage events on a system, a group of systems, or all the systems in the middleware repository.

Supported Sun Configuration and Service Tracker Releases

This utility is supported on middleware:

- Sun Configuration and Service Tracker 1.5_AMS
- Sun Configuration and Service Tracker 2.1_AMS
- Sun Configuration and Service Tracker 2.1U1_AMS

- Sun Configuration and Service Tracker 3.0
- Sun Configuration and Service Tracker 3.5
- Sun Configuration and Service Tracker 3.5.1
- Sun Configuration and Service Tracker 3.5.2
- Sun Configuration and Service Tracker 3.6.0

Features

There are three patterns of usage below:

Usage 1

./setcause -N HIERARCHY/NODENAME -p EVENT_NUM L1 L2 L3

This usage sets cause code for only certain events on a certain node. HIERARCHY/NODENAME represents a relative path under the middleware repository where the node data is stored.

Note – See section "SET CAUSE CODE PROCEDURE (Usage 1)" for more information.

Usage 2

./setcause [-i INPUTFILE or -G] -p PERIOD -r RULEFILE L1 L2 L3

-i INPUTFILE = set cause code for a list of nodes in INPUTFILE.

INPUTFILE can be created/edited from the setcause -h or -n output

-G = set cause code for all nodes (not recommended)

- Cause code will be applied only to shutdown/panic events.
- See section "SET CAUSE CODE PROCEDURE (Usage 2)" for more information.

PERIOD

PERIOD can be one of the following:

- INCEPTION
- LAST24HRS
- THISWK
- LASTWK
- THISMTH
- LASTMTH.
- THISQT
- LASTQT
- THISYR
- LASTYR
- CUSTOM start_date end_date

start_date and end_date format: mm/dd/yyyy

RULEFILE

RULEFILE contains a set of rules to indicate the time range for which cause code is applied. Each line in the rule file is in the following format:

```
<Day(s) of Week> <Time range in 24HRS format>
```

Example: If user wants to set cause code only for the time period outside business hours, for example, anytime but Mon-Fri 8am-7pm and Sat-Sun 9am-4pm, the rule file would look like:

```
MON,TUE,WED,THU,FRI 00:00:00 07:59:59
MON,TUE,WED,THU,FRI 19:00:01 23:59:59
SAT,SUN 00:00:00 08:59:59
SAT,SUN 16:00:01 23:59:59
```

The 4 rules above can be translated as:

Monday to Friday morning from 0am to just before 8am Monday to Friday evening from 7pm to just before midnight Saturday and Sunday morning from 0am to just before 9am Saturday and Sunday evening from 4pm to just before midnight

Set Cause Code Procedure (Usage 1)

- 1. Obtain cause code triplet values (L1 L2 L3) by using setcause -c
- 2. Use the findevent utility to list all outage events, e.g., shutdown and panic.
- 3. Use setcause -N hierarchy/nodename -p event_number L1 L2 L3 for a selected outage.

Set Cause Code Procedure (Usage 2)

This usage can be useful for the following cases:

- In the case of Test or non-production machines, the nature of downtime is not critical and is often planned. This usage can be used to mark outages for a group of machines as planned outages.
- A planned cause code can also be applied to outages that occurred during non-important hours (outside business hour or non prime-time hour).
- 1. Obtain cause code triplet values (L1 L2 L3) by using setcause -c
- 2. Setting cause code for a certain list of nodes requires an input file with the node list. To create an input file:
 - a. Change directories to the repository directory; type:

```
cd <RepositoryDirectoryName>
```

To discover the repository location, type: grep ROOT_PATH /var/opt/SUNWcst/cst.pref

b. Find the systems to be included in the file; type:

- c. Edit the mynodelist file as needed to remove any machines to which no cause codes are assigned.
- d. Find the events to be included in the file; type:

```
find . -type d |cut -b3- > mynodelist
```

Optionally, you can sort the node list.

e. To remove some machines from the list; type:

vi mynodelist ()

- 3. Specify time PERIOD where cause code will be applied. For example, the value of THISMTH will narrow down the event range to events happened within this month.
- 4. Create a Rule file. See RULE FILE section for more information. Rule file is used as a filter where user can specify daytime on specific weekday(s) that cause code will be applied.

app_event

Name

app_event - create application specific Sun Configuration and Service Tracker event

Synopsis

app_event "event-type" ["comment"]

Availability

SUNWcstu

Description

app_event command is used to create an application-specific Sun Configuration and Service Tracker event which will be recorded in the CST history log file in the directory /var/opt/SUNWcst.

Operands

event-type

event-type is defined by the user to specify the characteristics of the event.

Note – The event-type operand must be enclosed in double quotes.

Recommended format: "<word list><space><verb>"

<word list> could be the name of the application or entity to which a user can relate, potentially whose availability measurement would be useful.

<verb> would be a verb (preferably in the past tense). Possible verbs are:

- Started
- Stopped
- Restarted
- Halted
- Changed
- Installed
- Upgraded
- Unconfigured

comment

User comment about the application event.

Recommended format: <name>=<value>;<name>=<value>

It is a good practice to avoid white space around the = token. The name-value pairs should be separated by a semicolon (;) delimiter. For example, Comment= <comment>;Cause Code=<cause code>;Application Type=<application type>

Exit Status

The following exit values are returned:

TABLE 5-10 Exit Status Values

0	Successful operation
-1	Unable to resolve hostname
-2	UDP transport down on the system
-3	Sun Configuration and Service Tracker processes not running
-4	RPC timeout
-5	Command could not be completed successfully

Examples

The following example adds the machine password change as a Sun Configuration and Service Tracker event to cst history log.

/opt/SUNWcstu/bin/app_event "password changed" "admin=xyz"

If you want to track the password change automatically, you can add the following script to your crontab file, and run it at your desired time, for example, every hour or every day.

```
#!/bin/sh
# This script is used for creating a cst application event of
# event type string "Password Change" by calling cst command
# app_event. You need to add this script to your crontab file.
# Get the CST packet name
for i in SUNWcstu SUNWcst SUNWcstv SUNWcstve
do
        pkginfo $i 2> /dev/null 1> /dev/null
        if test \$? = 0
        then
                packname=$i
                break
        fi
done
# Get the installation base
instbase='pkginfo -r $packname'
```

```
# Set the full path to app_event
app_event=$instbase"/"$packname"/bin/app_event"
# Get the time info of the file: /etc/passwd
if test -f /tmp/cst_app_passwd
then
     ls -l /etc/passwd | awk '{print $6, $7, $8}' > /tmp/cst_app_passwd_new
        # Compare the time stamp of the passwd file, to see if there
        # any difference.
       diff /tmp/cst_app_passwd /tmp/cst_app_passwd_new > /tmp/cst_result
        result=`ls -l /tmp/cst_result | awk '{print $5}'`
        if test $result != 0
        then
                cp /tmp/cst_app_passwd_new /tmp/cst_app_passwd
                # Call cst_app_event to register event
             $app_event "Password Changed" "Changed by owner" 1> /dev/null
        fi
else
       ls -l /etc/passwd | awk '{print $6, $7, $8}' > /tmp/cst_app_passwd
fi
rm /tmp/cst_app_passwd_new
rm /tmp/cst_result
# End of the script
```

Note – app_event utility is not designed to handle high event volume. Do not use this utility to generate periodic or high-volume events as this may cause unnecessary traffic to the middleware server. app_event should be invoked on a per-event or occurrence basis to indicate changes to the system.

Files

/var/opt/SUNWcst/cst_history

addsunfire

Name

addsunfire - configures Sun Configuration and Service Tracker to track a SunFire system controller.

Description

The addsunfire command is provided as part of the Sun Configuration and Service Tracker middleware package and is to be run from the Sun Configuration and Service Tracker middleware system. The default location is:

/opt/SUNWcstv/bin

The command is used to configure Sun Configuration and Service Tracker to track data from a SunFire system controller. On successful execution, the command updates the *cst.conf* file with the configuration information.

Supported Sun Fire Platforms

The command can be used to set up Sun Configuration and Service Tracker tracking for SunFire 3800, 4800, 4810, and 6800.

Inputs

addsunfire is an interactive command and accepts the inputs described in the following table. Most of the data for the inputs can be gathered by running the showplatform (-v option) command on the Sun Fire system controller. Consult the Sun Fire system administration documentation for details on showplatform and setupplatform commands.

TABL	E 5-11	Inp	uts
IADEI		mp	uu

Input	Description
Platform Name	This is the name for the complete platform. It is recommended that a single word be used with no special characters or white-space. Usually, it coincides with the "System Description" as seen on the SunFire system controller.
SC Hostname	This is the network nodename of the MAIN system controller board. If a logical hostname is configured for the system controller, then that should be used instead of the MAIN system controller hostname.
	Do not use a SPARE system controller hostname.
SC Hostid	This is the MAIN system controller hostid. It is recommended that the hostid of SSC0 be used. The hostid can be obtained by running the showplatform (-v option) command.
	It is very important that the correct hostid be used or data corruption can occur.
SNMP Agent Enabled	This is a question posed to the user. It is expected that the user has checked that SNMP is enabled on the system controller and that all the SNMP settings are correct before answering this query with a 'y'. Any other input to this query will cause the command to exit if SNMP is not set up on the system controller, use the command setupplatform on the system controller.
SNMP Agent Port	This is the port number to which all SNMP requests should be sent. It is usually 161.

Input	Description
SNMP agent community	This is the public community string from the SNMP settings. If this value is inaccurate, all SNMP queries to the system controller will fail.
Hierarchy	This is the user-defined part of the hierarchy path (relative to the Sun Configuration and Service Tracker middleware repository) where the agent data is maintained. Sun Configuration and Service Tracker appends the Platform Name to the defined hierarchy path and maintains all the data files under it.
	The utility does not validate hierarchy paths. It is expected that the input provided is accurate.
Polling Interval	This is time interval (in seconds) between two successive Sun Configuration and Service Tracker probes. The minimum interval is 900s. The recommend (default) value is 1800s. The maximum is 86400s (once a day).

TABLE 5-11 Inputs

Note – The system controller data is recorded in the Sun Configuration and Service Tracker repository, on the Sun Configuration and Service Tracker server system, under the hierarchy:

<user-specified Hierarchy>/<user-specified platform name>

This path must be unique for each system controller, otherwise data corruption could result. It is recommended that you use a valid, non-generic hierarchy path and platform name when you add tracking for a system controller using the addsunfire command.

Format

The cst.conf file has a property specification defined for Sun Fire platform tracking.

SUNFIRE<tab><platform>|<sc-name>|<sc-hostid>|<snmp-port>|<snmp-comm unity>|<hierarchy>|<polling interval>|4800

Usage Examples

Example 1

Assuming the Platform name of the Sun Fire system to be sunfire1 and that the Sun Fire platform is configured with a logical hostname, sfl-sc.sun.com

```
Platform name (not the hostname, no white-space): sunfirel SC Hostname (if a virtual
hostname is configured, then it must be provided, otherwise use the main SC
hostname) : sfl-sc.sun.com
SC (main) Hostid (check showplatform -v on the main SC): 8308fcd3
Is SNMP agent enabled on the SC ? [y/n]: y
SNMP agent port (check SNMP settings the SC): 161
SNMP agent community (SNMP public community): public-comm
Hierarchy (Relative to CST repository, consult CST docs/faq): lab1/sunfires
Polling Interval (in seconds) (min 900, recommended default [1800]): 1800
Setting polling interval to 1800s.
Testing. This could take upto 20 minutes. Please wait...
Activating the system controller tracking daemon.
```

Exit Status

The command returns 0 on success and an integer value on failures. The cst.conf file is updated only on completion of a successful probe.

cstdecomm

Name

cstdecomm - EOL agent from reporting to Sun Configuration and Service Tracker Server/AMS.
Synopsis

cstdecomm [-t "mm/dd/yyyy hh:mm:ss"] [-h hierarchy] <a gentname>

Description

The purpose of the cstdecomm utility is to notify AMS that no further data for this host will be transmitted, and that the data on this system is stale. A system may be decommissioned from a server when the system is no longer going to remain operational or when the system is being moved out of that environment and AMS is to no longer consider it in the availability calculations.

Note – Before you can execute this utility, you must uninstall the agent package on the system to be decommissioned.

This utility should be executed from the server where the repository resides and requires root permission for execution.

The utility is designed to do the following:

1. Create the following event in the history file on the server for that monitored host:

Tracking Ended <timestamp> WEF:<dd:mm:yyyy hh:mm:ss>

2. Move the directory containing the agent data on the server to:

<cst db_root>/DECOMMISSIONED_AGENTS



Caution – Remove the SUNWcstu package on the agent before running the decommission utility for that agent on the Sun Configuration and Service Tracker server.

- An event is registered in the event history file on the server indicating "Tracking Ended" (from this server context). This event will be sent to AMS.
- On the server hosting the repository, the directory containing the monitored system's data will be moved under a directory named
 "DECOMMISSIONED_HOSTS" so that no new updates can be made to this data.
- The Summary email on the night of the event decommission will detect the change in the list of active hosts and notify AMS.

Sun Configuration and Service Tracker tracking of a monitored host is designed for and recommended to continue until the end of life (EOL) of that system. It should not be stopped even if it is moved to a different environment, except for specific short term Sun Configuration and Service Tracker software upgrade or a similar maintenance occurrence.

Parameters

-t mm/dd/yyyy hh:mm:ss

The date-time stamp can be added as an optional comment if the agent is already non-operational.

-h hierarchy

The relative path after the repository that was created to store the agent information. This option must be omitted if there is no hierarchy available.

agentname is the name of the agent as stored in the repository. This is a mandatory parameter, and agentname cannot refer to a Sun Configuration and Service Tracker server.

Supported Platforms

cstdecomm is supported on Solaris 2.6, 7, 8 9, and 10.

It is designed to work with Sun Configuration and Service Tracker 3.5.2 and Sun Configuration and Service Tracker 3.6.0. This utility does not work with versions below Sun Configuration and Service Tracker 3.0.

Examples

The parameter, -t, is an optional parameter

Nodes with Hierarchy

Example 1

./cstdecomm -t "05/12/2000 21:34:09" -h lab1/gp1 cstnode1.eng.sun.com

Example2

./cstdecomm -h lab1/group1 cstnode1.eng.sun.com

Nodes with no Hierarchy

Example 1

./cstdecomm -t "02/12/2000 12:23:03" cstnode2.eng.sun.com

Example 2

./cstdecomm cstnode2.eng.sun.com

Notes

- Sun Configuration and Service Tracker decommission utility must be run only when the agent machine is going to be in a non-operational state. Running this utility is not advised otherwise. Using this utility to do agent migration will result in unpredictable results.
- The agent will not be reported to the AMS once decommissioned. Please, use the command, pkgrm SUNWcstu, in the agent before using the cstdecomm utility.

Multi-domain/Node Systems

The process for decommissioning specific hosts of a multi-node/ domain platform is to use the utility mentioned above for those specific hosts. Ending tracking for the entire platform requires ending tracking on all the domains as well as the main and spare system controllers/service processors (SCs/SSPs). The Decommission utility has to be used iteratively on each of the domains and the SCs and SSPs until all the directories are moved to:

<cst root_path>/DECOMMISSIONED_AGENTS

Examples of Usage

Not running a pkgrm SUNWcstu in the agent machine before decommissioning it from the Sun Configuration and Service Tracker server leads to unpredictable results.

The middleware or the platform in multi-domain systems cannot be decommissioned.

Chapter 6

Troubleshooting Sun Configuration and Service Tracker

Because Sun Configuration and Service Tracker is a client-server application, the communication between the applet, the server, and the agent on the host being tracked can be unstable. This may be because either the host or the server or the Sun Configuration and Service Tracker daemon processes in them may be down momentarily. This chapter lists error messages and possible solutions.

Send comments to the Sun Configuration and Service Tracker Development Team by clicking on the Comments button at the bottom of the Sun Configuration and Service Tracker GUI.

Note – You must run Netscape Communicator in order to use the Comments button, since Netscape Navigator does not support an email capability. If using Netscape Navigator, send email to cst-master@eng.sun.com.

Error Messages

This section contains information about the following error messages:

- "Error, cannot set up TCP connection" on page 6-2
- "Wrong Component (Agent vs Server) Selected During Install" on page 6-2
- "Sun Configuration and Service Tracker Package Install Fails Repository is a Sub-folder in /var/opt/SUNWcst" on page 6-3
- "Error in Compiling Statistics" on page 6-3

- "Site Registration Fails With Customer ID and Key" on page 6-3
- "Cannot View FRUI Data on SF15K SC" on page 6-4
- "Missing FRU Data for Mid-frame Sun Fire System Controllers" on page 6-4
- "Sun Configuration and Service Tracker Platform Data Missing on Sun Fire 15K Main SC" on page 6-5

Error, cannot set up TCP connection

Problem: This might happen when a user clicks the GUI console whereas the Sun Configuration and Service Tracker Server has been restarted.

There are two possible causes of this error:

 Sun Configuration and Service Tracker server daemon (cstd.svr) is down on the server machine.

Suggested action: Make sure cstd.svr is running on the machine and it has not been restarted since the GUI was invoked; type:

ps -ef|grep cstd.svr

• There is a firewall running on the server machine.

Suggested action: Consult the system administrator who owns the server. If a firewall is present, the firewall must be configured with a range of TCP ports through which Sun Configuration and Service Tracker can pass.

After the firewall is configured, enter the TCP port range into the Sun Configuration and Service Tracker file on the Sun Configuration and Service Tracker agent:/var/opt/SUNWcst/files/port_cfg

Refer to the details in "Network Protocols" on page 4-9.

Wrong Component (Agent vs Server) Selected During Install

Problem: The agent component was selected during the installation.

Suggested action: To get the Server/Agent option back into the installation, you must remove the existing Sun Configuration and Service Tracker package using pkgrm. Then manually clean up the /var/opt/SUNWcst directory, and reinstall the Sun Configuration and Service Tracker package.

Note – This action must be taken only in the case of a new install.

Sun Configuration and Service Tracker Package Install Fails - Repository is a Sub-folder in /var/opt/SUNWcst

Problem: The Sun Configuration and Service Tracker package install fails when the database repository is a sub-folder in /var/opt/SUNWcst.

Suggested action: Create the folder for the database repository outside of /var/opt/SUNWcst. If one or more of the Sun Configuration and Service Tracker agents are attached to this agent, the move could affect the functioning of the attached agents.

Note – For details, see "Move Agent Data to a Different Hierarchy" on page 4-16.

Error in Compiling Statistics

Problem: In the statistics folder, the Total Time prints out an Error message like the following one:

ERROR: Time stamp incorrect on event #25

Suggested action: To fix the offending event details, call your local Sun service provider.

Site Registration Fails With Customer ID and Key

Problem: Registration fails when the provided customer ID and registration key is used in the Sun Configuration and Service Tracker console.

Suggested action: This can happen if the registration key is used on a system that is different from the one that sent out the registration request. Request a new registration key from the system generating the error.

Note – The registration key is based on the host ID and must be used only on the system for which it is generated.

Cannot View FRUI Data on SF15K SC

Problem: Sometimes the FRU data on the SF15K system controller is not available to view.

Suggested action: Sun Configuration and Service Tracker might still be collecting FRU data. This process can take 10-15 minutes to complete.

You can turn off this feature. In the cst.conf file, set the SF15K_FRU_INTERVAL parameter to 0 and restart Sun Configuration and Service Tracker. For more details and the syntax of the cst.conf file, refer to "Tuning Sun Configuration and Service Tracker Trigger Intervals" on page 4-11.

Missing FRU Data for Mid-frame Sun Fire System Controllers

Problem: This might happen if the required library libfrurmi.so and other related files are not in the paths searched by Sun Configuration and Service Tracker.

Sun Fire mid-frame systems are Sun Fire 3800, 4800, 4810, and 6800.

Suggested action: Locate the library libfrurmi.so and related files, and modify the script in /opt/SUNWcstve/bin/cstrfru_start.sh. Remember that this applies only to the SUNWcstve package files.

For example, if the libfrurmi.so and related files are in the */opt/SUNWfrusg/lib* directory, change the script as shown:

```
#!/bin/sh
CSTVAR=/var/opt/SUNWcst
CSTBIN="`dirname $0`"
if [ -f "/opt/SUNWfrusg/lib/libfrurmi.so" ]; then
LD_LIBRARY_PATH=
/opt/SUNWfruid/lib:/opt/SUNWfrusg/lib:${LD_LIBRARY_PATH}
export LD_LIBRARY_PATH
${CSTBIN}/cstrfru $1 $2 $3 $4 $5 $6
else
echo "cannot find shared object libfrurmi.so" >
/tmp/cstrfru.err
fi
```

Sun Configuration and Service Tracker Platform Data Missing on Sun Fire 15K Main SC

Problem: Sun Configuration and Service Tracker platform data is missing on Sun Fire 15K MAIN system controller. This might be because the root user is not in any of the platform groups, such as platadmn, platoper, and platsvc.

Suggested action: Modify /etc/group and add root user to one of the platform groups. This can be verified by running the showfailover -r command as root. The command should return either MAIN or SPARE. It should not return any errors about insufficient platform privileges.

Error Messages

Chapter 7

Sun Configuration and Service Tracker Interface Reference

This chapter contains two tables. One table describes functionary found in the Sun Configuration and Service Tracker Console. The second table contains the Event Cause code hierarchy.

Sun Configuration and Service Tracker Console Functionality Descriptions

TABLE 7-1 lists the folders, buttons, and other features found in the Sun Configuration and Service Tracker console..

Name	Element Type	Location	Description or Action
>>	Button	Dialog box for Add/Modify in Notification tab	Moves selected events from various event groups to the "Selected Events" list.
<<	Button	Dialog box for Add/Modify in Notification tab	Removes selected events from "Selected Events" lists.
About CST	Iconized Button	Main Window	Contains version information for the Sun Configuration and Service Tracker release.
Action	Field	History tab	Displays the action taken upon the hardware or software identified by the label and description.

 TABLE 7-1
 Sun Configuration and Service Tracker Console

Name	Element Type	Location	Description or Action
Add	Button	Notification tab	Adds new email address to email recipients list.
Add All	Button	Dialog box for Add/Modify in Notification tab	Moves all events from various event groups to the "Selected Events" list.
All Events	Button	Print tab	Selects the report option to send all CST history events to be printed or emailed in a report.
Append Comments	Button	History tab	Allows user to input additional comments for the highlighted event.
Apply	Button	Various tabs	Applies the setting change entered by the user.
Cancel	Button	Various tabs	Cancels an input change.
Cluster	sub tab	History and Configuration tabs	Displays information about Sun Cluster 3.0, if installed. Highlighted only if available.
Cluster & Volume Manager Events	Menu	Dialog box for Add/Modify in Notification tab	Lists all cluster and volume manager events.
Comments	Field	History tab	Displays any automatic or user comments associated with an event.
Configurations	tab	Main window	Contains inception configuration and current configuration details.
Create Service Event	Button	History tab	Makes the User Comments field writable to record a service event that captures specific actions taken on the system.
CST	Button	Main window	Displays information about the installed Sun Configuration and Service Tracker software, such as its version number.
CST Status	Field	Main window	Shows whether the Sun Configuration and Service Tracker software on the displayed system is currently up, down, or not responding.
Current Configurations	Button	Configurations tab	Displays a snapshot of the current system configuration.
Current Event	Field	History tab	The event currently selected (highlighted) in the History event log.
Custom Info	1. Sub tab	1. History & Configuration tabs	1. Displays user-entered information about a specific system.
	2. Button	2. Print tab	2. Prints or emails user-entered information about a specific system.

Builden and Service Hacher Comboli

Name	Element Type	Location	Description or Action
Customer Contact	Field	Admin dialog box	Stores customer contact information for a system admin contact and an alternative customer contact. The fields store a name, phone number, pager number, and email address for each.
D:H:M:S	Field	Statistics tab	Days: Hours: Minutes: Seconds
Date/Time	Field	History tab	Time stamp when the event occurred.
Decommis- sioned_Agents	Node in hierarchy	Main window/ Hierarchy	Lists agents that are no longer tracked for availability.
Delete	Button	Preferences tab	Deletes an existing email address entry from the Notification tab.
Description	Field	History tab, Configuration tab	User-level description of a component of the system configuration.
Device Group	Radio Button	Cluster sub tab	Displays Device Group information about this Cluster. Information is tabularized into Groupname, Primary, Secondary, Spare, inactive and status.
DiskGroup	Radio Button	Volume Manager tab	Displays information about the available Disk Groups as created by the Veritas Volume Manager in this System. Information is tabularized as Name, Assoc, Length, State, K-State.
DiskMedia	Radio Button	Volume Manager tab	Displays information about the Disk Media contents of the Veritas Volume Manager.Information is tabularized as Name, Assoc, Length, State, and K-State.
Down%	Field	Statistics tab	Percentage of time the system was down.
Edit Custom Info	Button	Configurations tab	Opens a dialog box to enter customer information, including customer name, street address, city, state, country, and ZIP or postal codes.
Email	Field	Preferences tab	Allows user to enter an individual or group address to receive email whenever an event is detected.
Email Address	Field	Print tab	Sets the email address that will receive the report.
Email Recipients	Field	Preferences tab	Displays all individual or group addresses that will receive email whenever an event is detected.
Enterprise View	Menu Item	Main window	Causes the Sun Configuration and Service Tracker console to re-check system information and display the most recent results for the entire enterprise.
Event	Field	History tab	Displays the type of system event, such as a reboot or a software change, detected by Sun Configuration and Service Tracker.

TABLE 7-1	Sun (Configuration	and Service	Tracker	Console

Name	Element Type	Location	Description or Action
Events Assigned	Menu	Notifications tab	Lists events for which notification is sent to the email recipient selected in the email recipients menu in the same tab.
Event Cause Code	Menu	History tab, under the Why? button	A selection made through the Event Cause Code Dialog box, where the reason for an event can be manually defined.
Exit	Button	Log Out menu	Closes current session.
FRU Information	Radio Button	Installed Hardware	Displays information about the static Field Replaceable Units information found in this system. Information is further tabularized as Label, Description, Serial#, Part#, Revision#, Hierarchy and others. Highlighted only if available.
Get All	Button	History tab	Pulls all events from the repository and displays them.
Get More	Button	History tab	Increases the number of displayed events from 11 to 22.
Get Statistics	Button	Statistics tab	Selects a range of time, retrieves the uptime and downtime statistics for that period, and displays them.
Global Event Cause Code Update	Iconized button	Main	Allows assignment of a cause code for an outage event on all the agents monitored by this middleware.
Hierarchy	Field	History or Configurations tab under Installed Hardware sub tab	Displays the name for the collection of systems tracked by the Sun Configuration and Service Tracker server.
History	tab	Main window	Contains the event log, comments log, and configuration changes detected at the time of each event.
Inception Configuration	Button	Configurations tab	Displays a snapshot of system configuration at the time of the first Sun Configuration and Service Tracker install.
Installed Hardware	sub tab	History tab	Displays a list of hardware installed during the highlighted event, including information such as its part number, serial number, and hierarchy.
Label	Field	Various sub tabs	Displays the official name for a component of the configuration, for example, host ID or sysboard0.
Log Out	Button	Main Window	Closes current session.
Member Status	Radio	Cluster sub tab	Displays the status of all the nodes in the cluster. Information tabularized into Nodename, NodeId and State.
Modify	Button	Notification tab	Allows addition of events to an existing email address.

TABLE 7-1 Sun Configuration and Service Tracker Console

-			
Name	Element Type	Location	Description or Action
Notification	tab	Mail window	Contains list of email recipients to receive email for selected events.
Other Events	Menu	Dialog box for Add/Modify in Notification tab	Lists all other events not listed in Outage, System, Cluster & Volume Manager event group. Includes Sun Configuration and Service Tracker- generated events.
Outage Events	Menu	Dialog box for Add/Modify in Notification tab	Lists all events that pertain to system outages.
Peripheral Hardware	Radio Button	Installed Hardware	Displays information about the available peripheral hardware found in this system. Information is further tabularized as Label, Description, Serial#, Part#, Revision#, hierarchy, and others.
Planned	1. Menu choice	1. Why? button, under Cause Code dialog box	1. Flag set by the user to confirm that the event was pre- planned and users affected by the event were notified.
	2. Field	2. History tab	2. Displays whether an event was marked as planned or unplanned by the user.
Plexes	Radio Button	Volume Manager tab	Displays the Plexus information as created by the Veritas Volume Manager in this system. Information is tabularized as Name, Assoc, Length, State, and K-State.
Preferences	tab	Main window	Contains a list of email addresses to be notified when Sun Configuration and Service Tracker events occur.
Print	tab	Main window	Contains options to print or email reports.
Printer	Field	Print tab	Sets the name of the printer that will print the selected report.
Quorum Votes	Radio Button	Cluster sub tab	Displays the Quorum Votes information about this Cluster. Information is tabularized as Name, type, present, possible, needed and status.
Refresh	Menu Item	Main window	Causes the Sun Configuration and Service Tracker console to re-check system information and display the most recent results.
Remove All	Button	Dialog box in Notification tab	Deletes all events from the selected events list.
Resource Group Information	Radio Button	Cluster sub tab	Displays the resource group information for this cluster. This information is tabularized as RGName, State, Configmode, PathPrefix.
Resource List by Group	Radio Button	Cluster sub tab	Displays the resource list for this cluster by groups. This information is tabularized into RGName and Resources.

TABLE 7-1	Sun Configuration	and Service	Tracker	Console
-----------	-------------------	-------------	---------	---------

Name	Element Type	Location	Description or Action
Resource Information	Radio Button	Cluster sub tab	Displays the resource information for this cluster. Information tabularized as Rname, Type, RState, Status, Status Information.
Resource Type Information	Radio Button	Cluster sub tab	Displays information about the Resource Type for this Cluster. Information Tabularized as RType, RTVersion, BaseDir, Start, Stop and RTpkgs.
Revision #	Field	History tab, Configurations tab	Displays the revision number of the hardware or software identified by the label and description.
Selected Event	Button	Print tab, under CST History sub tab	Sets the report to only display information for the highlighted event.
Serial #	Field	History tab, Configurations tab	Displays the serial number of the hardware identified by label and description.
Site Info	Iconized button	Main Window	Opens a dialog box to enter customer and other global information to register the site.
Site Registration	Iconzied button	Main window	Opens a dialog box to enter customer and other global information about this location.
Software Packages	sub tab	History tab, Configurations tab	Displays a list of software packages installed on the system.
Software Patches	sub tab	History tab, Configurations tab	Displays a list of patches installed on the system.
Solaris Internal Info	sub tab	History tab, Configurations tab	Lists the key Solaris internal parameters tracked by Sun Configuration and Service Tracker.
Statistics	tab	Main window	Contains a suite of statistics breakdowns, extracted from the data collected by Sun Configuration and Service Tracker.
Sub Disks	Radio button	Volume Manager tab	Displays the Subdisks information as partitioned by the Veritas Volume Manager in this System, Information is tabularized as Name, Assoc, Length, State, and K-State.
Summary	Radio Button	Cluster sub tab	Displays the summary information of all the nodes in this cluster. Information is tabulated into name and value.
System Displayed	Field	Main window	Shows either the name of the system whose events and facts are being displayed, the name of the E10K platform, or unknown host.
System Events	Menu	Dialog Box for Add/Modify in Notification tab	Lists all system configuration change events.

TABLE 7-1 Sun Configuration and Service Tracker Console

Name	Element Type	Location	Description or Action
System Hardware	Radio Button	Installed Hardware	Displays information about the hardware found in this system. Information is further tabularized as Label, Description, Serial#, Part#, Revision#, hierarchy, and others.
System Info	Field	Configurations tab, under the Edit Custom Info button	Allows the user to enter the serial number and type of system.
System Information	sub tab	History tab, Configurations tab	Displays system information such as the system model, host name, and number of CPUs.
System Status	Field	Main window	Shows whether the displayed system is currently up or down.
System View	Menu Item	Main Window	Displays the latest information for the selected system.
Time Down	Field	Statistics tab	Displays the total time the system was down.
Time Up	Field	Statistics tab	Displays the total time the system was up.
Total Time	Field	Statistics tab	Displays the total time for which Sun Configuration and Service Tracker has collected data.
Transport Path	Radio Button	Cluster sub tab	Displays information about the Transport path for this cluster. Information is tabularized as Endpoint, Endpoint and Status.
Unplanned	Menu choice	Why? button, under Cause code dialog box	Flag set by the user to confirm that the event was not pre- planned, and that users potentially affected by the event were not pre-notified.
Up%	Field	Statistics tab	Displays the percentage of time the system was up.
User Comments	Field	History tab	Contains comments relating to a specific event, either provided by the user or automatically generated by Sun Configuration and Service Tracker.
Volume Manager (VM)	Sub-tab	History and Configuration tabs	Displays a list of information about the Veritas VM if installed. The information is tabulated as Name, Assoc, Length, State and K-State. Highlighted only if available.
Volumes	Radio Button	Volume Manager tab	Displays Volume information as created by the Veritas Volume Manager in this system. Information is tabularized as Name, Assoc, Length, State, K-State.
Why?	Button	History tab	Assigns a reason (cause code) for the new or highlighted event.

Event Cause Code Hierarchy

TABLE 7-2 shows the hierarchy of Event Cause Codes for the WHY? button

TABLE 7-2	Event	Cause	Codes
-----------	-------	-------	-------

Top Tab	Category	Event Cause Code
Undefined	Undefined	Undefined

Top Tab	Category	Event Cause Code
Planned	Undefined	Undefined
	System Management	Undefined
		Performance Management
		Configuration Management
		User & Security Management
		Storage Management
		Backup
		Monitoring
		Comment
		Planned/Scheduled Reboot
		Other
	System Hardware	Undefined
		CPU Module
		CPU System Board
		Memory
		I/O Board UPgrade/Maintenance
		Power Sybsystem UPgrade/Maintenance
		Cooling Sybsystem Upgrade/Maintenance
		Disk Upgrade/Maintenance
		Tape Upgrade/Maintenance
		Other
	System Software	Undefined
		Patch Installation
		Device Driver
		System Management Tool
		Configuration Problem
		Naming Service Problem
		Middleware Upgrade/Maintenance
		Operating System Upgrades
		Installation
		Removal
		Other

 TABLE 7-2
 Event Cause Codes

Top Tab	Category	Event Cause Code
Planned	Application	Undefined
		Patch Installation
		Application Upgrades
		Database Upgrade/Maintenance
		Application/Database Schema Management
		Configuration
		Batch Processing
		Other
		Installation
		Removal
	Network	Undefined
		Network Hardware Upgrade/Maint.
		Network Software Upgrade/Maint.
		Circuit
		Configuration
		Configuration
	Environmental	Undefined
		Utility Power
		Facilities
		Other

TABLE 7-2Event Cause Codes

Top Tab	Category	Event Cause Code
Unplanned	Undefined	Undefined
	System Overload	Undefined
		System Performance
		Storage
		Network
		Disk Space Full
		Interface Congestion
		Other
	Procedural Failure	Undefined
		Undocumented Planned Outage
		System Config. Error
		Planned Downtime Past Maintenance Window
		Business Process
		Version Incompatibility
		Code Change Resulted in Error
		Operator Error
		Data Entry Error
		Distributed Code Corruption
		Tape Backup
		Other

TABLE 7-2Event Cause Codes

Top Tab	Category	Event Cause Code
Unplanned	System Hardware Failure	Undefined
		CPU Module
		CPU System Board
		Memory
		I/O Board
		System Interface Board
		Backplane
		Power Subsystem
		Cooling Subsystem
		Cable
		Disk
		Tape
		Network
		SAN/Storage
		Cluster Software
		Other
	System Software Failure	Undefined
		Operating System
		Device Driver
		Network Interface
		System Management Tool
		File Corrupt
		File Missing
		Daemon Hung or Dead
		Configuration Problem
		Requiring Patch or Upgrade
		Naming Service Problem
		Other
	Application Failure	Undefined
		End User Application
		User Interface
		Middleware
		Database
		Performance
		Configuration
		Firewall Problem
		Other

TABLE 7-2Event Cause Codes

Top Tab	Category	Event Cause Code
Unplanned	Network Failure	Undefined
		Procedural
		Network Hardware
		Network Software
		Loss of Physical Connectivity
		Depletion of Resources
		Carrier
		Circuit
		Configuration
		Routing
		Environmental
		Other
	Environmental	Undefined
		Utility Power
		UPS
		Generator
		Air Condition
		Fire
		Plumbing
		Natural Disaster (Flood, Earthquake)
		Other
	Known	Undefined
	Unknown	Undefined

 TABLE 7-2
 Event Cause Codes

Event Cause Code Hierarchy

Index

Symbols

<< 7-1 >> 7-1

Numerics

128 bit encryption 1-24

Α

About CST 7-1 Action 7-1 Add 7-2 addsunfire 1-15 agent 2-4, 2-11, 2-14 Agent install 2-4 All Events 7-2 AMS 1-2 Apache 2-6 API 1-21 app_event 1-21 Append Comments 7-2 Apply 7-2 asset.conf 1-10 attach 2-23 attach an agent 2-22 automated backup 1-2

В

backup 1-9

board power-on 1-3, 1-13 boot 1-3

С

Cancel 7-2 cause code 2-23 cause code 1-10 Cluster 7-2 cluster Device Group Information 1-15 failover events 1-16 membership 1-15 Membership Status 1-15 nodes 1-15 Quorum Votes 1-15 **Resource Group Information 1-15** Resource List 1-15 **Resource Type Information 1-15** Summary Information 1-15 Transport Path 1-15 Cluster & Volume Manager Events 7-2 Cluster node failovers 1-3 Cluster resource group failovers 1-3 command line 2-23 Comments 7-2 configuration management 1-6 **Configurations 7-2** changes 1-2

Disk group 1-19 Disk Media 1-19 Plexes 1-19 Sub Disks 1-19 tab 1-5 Volumes 1-19 Create Service Event 7-2 CST 7-2 agent installation 2-14 console 1-3 data 1-9 database 2-6 on Clusters 1-15 repository 1-9 server 1-9 server requirements 2-4 status 7-2 CST 1.0.1 2-18 CST 1.1.3 AMS 2-18 CST console 1-5 CST packages removal 1-3 upgrade 1-3 CST Server Requirements 2-4 cst.pref 1-10 cst history 1-10 cstattach 2-22, 2-24, 2-25 **Current Configurations 7-2** Current Event 7-2 custom information 1-3, 7-2 Customer Contact 7-3

D

data files 1-9 Date/Time 7-3 Decommissioned_Agents 7-3 Delete 7-3 Description 7-3 desktops, 4u 1-12 detachment of system hardware 1-3 Device Group 7-3 DHMS 7-3 disk space requirements 2-2 DiskGroup 7-3 DiskMedia 7-3 domains 1-3, 1-14 additions 1-3 changes 1-13, 1-14 deletions 1-3 Down% 7-3 dynamic attachment 1-3

Ε

E10K 2-24, 2-25, 2-26 E10k 2-24 Edit Custom Info 7-3 Email 7-3 address 7-3 recipients 7-3 Event 7-3 assigned 7-4 Cause Code 7-4 measurement precision 1-2

F

fresh installation, see new installation FRU 1-5, 2-5 information 7-4

G

Get All 7-4 Get More 7-4 Get Statistics 7-4 Global Event Cause Code Update 7-4 GUI 2-23

Η

hang 1-3 hardware changes, domains 1-3 hierarchical directory structure 1-9 hierarchy 2-24, 7-4 high-end 1-12 history 7-4 file 1-9 folder 1-19 log 1-21

I

Inception Configuration 7-4 Installed Hardware 7-4 installed hardware 1-4, 1-5

J

JDK 1.1.5 1-12

L

Label 7-4 location.conf 1-10 log 1-6

Μ

Member Status 7-4 middleware 1-5, 1-9, 2-4, 2-6, 2-10, 2-11, 2-14 mid-range 1-12 Modify 7-4 multi-domain 2-21 multi-user availability 1-2

Ν

new installation 2-3, 2-7 Notification 7-5

0

online documentation Preface-2 OS upgrade 1-3, 2-7, 2-11 Other Events 7-5 Outage Events 7-5

Ρ

panic 1-2, 1-3 patch hardware 1-2 software 1-2 Peripheral Hardware 7-5 Planned 7-5 Platform configuration changes 1-14 Plexes 7-5 Preferences 7-5 Preferences file 1-9 Print 7-5 Printer 7-5 probe.current 1-10 probe.inception 1-10

Q

Quorum Votes 7-5

R

reboot 1-2, 1-3, 1-6 Refresh 7-5 Reinstall 2-3 Resource Group Information 7-5 Resource Information 7-6 Resource List by Group 7-5 Resource Type Information 7-6 Revision # 7-6 runlevel change 1-3

S

SC 2-21 secure data feed 1-2 Selected Event 7-6 Serial #7-6 Server install 2-3 server platforms, 4d- & 4u-based 1-12 service events 1-6 service.conf 1-10 shutdown 1-2 Site Info 7-6 Site Registration 7-6 snapshot 1-4 software installation 1-3 removal 1-3 software packages 1-4, 7-6 software patches 1-4, 7-6 addition 1-3 removal 1-3 Solaris Preface-2, 1-12 documentation Preface-2 Internal Info 7-6 **Operating Environment 1-4** Sparc III 1-13

SRS Net Connect, transport 1-24 SSC 2-24 SSP 1-13, 2-21, 2-24, 2-25, 2-26 ssp.tar 2-26 Statistical report 1-6 Statistics 7-6 Sub Disks 7-6 Summary 7-6 Sun Cluster 3.0 1-15 3.1 1-15 Sun Enterprise 10000 1-12, 1-13 Sun Fire 1-12, 1-14 12K 1-14 15K 1-14. 2-23 3800 1-14 4800 1-14 4810 1-14 6800 1-14 high-end 1-14 midrange 1-14 system controllers 2-5 Sun platforms, multi-domain 1-13 SUNWcst 2-21 SUNWcstu 5-33 SUNWcstv 2-6 SUNWcstve 2-6 SUNWfrusg 2-5 Supported Systems 1-12 system administration 1-5 availability 2-23 configuration 1-2, 2-23 configuration changes 1-14 controller, events 1-14 controllers 1-14 events 2-23 hardware 7-7 information 1-4 parameter changes 1-2 shutdown 1-3 System Displayed field 7-6 System Events field 7-6

System Information 7-7 System Status field 7-7 system.conf file 1-10

Т

text repository 1-2 three-tier architecture 1-2 Time Down 7-7 Time Up 7-7 timestamps 1-2 Total Time 7-7 Transport Path 7-7

U

UFS 2-6 Uninstall 2-28 UNIX Preface-2, 1-21, 2-4 Unplanned 7-7 Up% 7-7 uptime statistics 1-2 User Comments 7-7 user.conf 1-10

V

viewing events 1-5 VM, see Volume Manager Volume Manager 1-18, 7-7 configuration 1-4 Volumes 7-7

W

Why? button 7-7