

Oracle® Solaris 10 8/11 Installation Guide: Basic Installations

Copyright © 2011, 2012, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS. Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle America, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Ce logiciel et la documentation qui l'accompagne sont protégés par les lois sur la propriété intellectuelle. Ils sont concédés sous licence et soumis à des restrictions d'utilisation et de divulgation. Sauf disposition de votre contrat de licence ou de la loi, vous ne pouvez pas copier, reproduire, traduire, diffuser, modifier, breveter, transmettre, distribuer, exposer, exécuter, publier ou afficher le logiciel, même partiellement, sous quelque forme et par quelque procédé que ce soit. Par ailleurs, il est interdit de procéder à toute ingénierie inverse du logiciel, de le désassembler ou de le décompiler, excepté à des fins d'interopérabilité avec des logiciels tiers ou tel que prescrit par la loi.

Les informations fournies dans ce document sont susceptibles de modification sans préavis. Par ailleurs, Oracle Corporation ne garantit pas qu'elles soient exemptes d'erreurs et vous invite, le cas échéant, à lui en faire part par écrit.

Si ce logiciel, ou la documentation qui l'accompagne, est concédé sous licence au Gouvernement des Etats-Unis, ou à toute entité qui délivre la licence de ce logiciel ou l'utilise pour le compte du Gouvernement des Etats-Unis, la notice suivante s'applique:

U.S. GOVERNMENT RIGHTS. Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle America, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

Ce logiciel ou matériel a été développé pour un usage général dans le cadre d'applications de gestion des informations. Ce logiciel ou matériel n'est pas conçu ni n'est destiné à être utilisé dans des applications à risque, notamment dans des applications pouvant causer des dommages corporels. Si vous utilisez ce logiciel ou matériel dans le cadre d'applications dangereuses, il est de votre responsabilité de prendre toutes les mesures de secours, de sauvegarde, de redondance et autres mesures nécessaires à son utilisation dans des conditions optimales de sécurité. Oracle Corporation et ses affiliés déclinent toute responsabilité quant aux dommages causés par l'utilisation de ce logiciel ou matériel pour ce type d'applications.

Oracle et Java sont des marques déposées d'Oracle Corporation et/ou de ses affiliés. Tout autre nom mentionné peut correspondre à des marques appartenant à d'autres propriétaires qu'Oracle.

Intel et Intel Xeon sont des marques ou des marques déposées d'Intel Corporation. Toutes les marques SPARC sont utilisées sous licence et sont des marques ou des marques déposées de SPARC International, Inc. AMD, Opteron, le logo AMD et le logo AMD Opteron sont des marques ou des marques déposées d'Advanced Micro Devices. UNIX est une marque déposée d'The Open Group.

Ce logiciel ou matériel et la documentation qui l'accompagne peuvent fournir des informations ou des liens donnant accès à des contenus, des produits et des services émanant de tiers. Oracle Corporation et ses affiliés déclinent toute responsabilité ou garantie expresse quant aux contenus, produits ou services émanant de tiers. En aucun cas, Oracle Corporation et ses affiliés ne sauraient être tenus pour responsables des pertes subies, des coûts occasionnés ou des dommages causés par l'accès à des contenus, produits ou services tiers, ou à leur utilisation.

Contents

| | |
|--|----|
| Preface | 5 |
| 1 Planning for a Oracle Solaris Installation From CD or DVD Media (Tasks) | 9 |
| System Requirements and Recommendations | 10 |
| Oracle Solaris Installation Program GUI or Text Installer Requirements | 12 |
| General Disk Space Planning and Recommendations | 13 |
| Disk Space Recommendations for Software Groups | 15 |
| Checklist for Installation | 17 |
| Where to Find Additional Installation Information | 28 |
| 2 Installing With the Oracle Solaris Installation Program For UFS File Systems (Tasks) | 31 |
| SPARC: Performing an Installation or Upgrade With the Oracle Solaris Installation Program for UFS File Systems | 31 |
| ▼ SPARC: To Install or Upgrade With the Oracle Solaris Installation Program | 32 |
| x86: Performing an Installation or Upgrade With the Oracle Solaris Installation Program for UFS File Systems | 45 |
| ▼ x86: To Install or Upgrade With the Oracle Solaris Installation Program With GRUB | 45 |
| 3 Installing With the Oracle Solaris Interactive Text Installer for ZFS Root Pools (Planning and Tasks) | 63 |
| ZFS Root Pool Installation (Planning) | 63 |
| What's New in the Oracle Solaris 10 8/11 Release | 64 |
| What's New in the Solaris 10 10/09 Release | 64 |
| Performing Initial Installation With the Oracle Solaris Interactive Text Installer for ZFS | 65 |
| ▼ SPARC: How to Install a ZFS Root Pool | 65 |
| x86: Performing an Initial Installation With the Oracle Solaris Interactive Text Installer for ZFS | 77 |
| ▼ x86: To Install With the Oracle Solaris Interactive Text Installer With GRUB for ZFS | 77 |

Index91

Preface

This book describes how to use CD or DVD media to install the Oracle Solaris operating system (OS) on a non-networked system.

This book does not include instructions about how to set up system hardware or other peripherals. This book provides instructions for installing both UFS file systems and ZFS root pools.

Note – This Oracle Solaris release supports systems that use the SPARC and x86 families of processor architectures. The supported systems appear in the *Oracle Solaris OS: Hardware Compatibility Lists*. This document cites any implementation differences between the platform types.

In this document, these x86 related terms mean the following:

- x86 refers to the larger family of 64-bit and 32-bit x86 compatible products.
- x64 relates specifically to 64-bit x86 compatible CPUs.
- "32-bit x86" points out specific 32-bit information about x86 based systems.

For supported systems, see the *Oracle Solaris OS: Hardware Compatibility Lists*.

Who Should Use This Book

This book is intended for system administrators who are responsible for installing the Oracle Solaris OS. This book provides basic Oracle Solaris installation information for system administrators who perform infrequent Solaris installations or upgrades.

If you need advanced Oracle Solaris installation information, see “[Related Books](#)” on page 6 to find the book that describes the information.

Related Books

Table P-1 lists documentation for system administrators.

TABLE P-1 Are You a System Administrator Who is Installing Oracle Solaris?

| Description | Information |
|---|---|
| Do you need system requirements or high-level planning information? Or want a high-level overview of Oracle Solaris ZFS root pool installations, GRUB based booting, Oracle Solaris Zones partitioning technology, or creating RAID-1 volumes? | <i>Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade</i> |
| Do you need to upgrade or patch your system with almost no downtime? Save system downtime when upgrading by using Live Upgrade, a feature of Oracle Solaris. | <i>Oracle Solaris 10 8/11 Installation Guide: Live Upgrade and Upgrade Planning</i> |
| Do you need to install a secure installation over the network or Internet? Use WAN boot to install a remote client. Or, do you need to install over the network from a network installation image? The Oracle Solaris installation program steps you through an installation. | <i>Oracle Solaris 10 8/11 Installation Guide: Network-Based Installations</i> |
| Do you need to install Oracle Solaris on multiple machines? Use JumpStart to automate your installation. | <i>Oracle Solaris 10 8/11 Installation Guide: Custom JumpStart and Advanced Installations</i> |
| Do you need to install or patch multiple systems quickly? Use Flash Archive, a feature of Oracle Solaris to create a flash archive and install a copy of the OS on clone systems. | <i>Oracle Solaris 10 8/11 Installation Guide: Flash Archives (Creation and Installation)</i> |
| Do you need to back up your system? | Chapter 22, “Backing Up and Restoring UFS File Systems (Overview),” in <i>System Administration Guide: Devices and File Systems</i> |
| Do you need troubleshooting information, a list of known problems, or a list of patches for this release? | <i>Oracle Solaris Release Notes</i> |
| Do you need to verify that your system works on Oracle Solaris? | SPARC: <i>Solaris Sun Hardware Platform Guide</i> |
| Do you need to check on which packages have been added, removed, or changed in this release? | <i>Oracle Solaris Package List</i> |
| Do you need to verify that your system and devices work with Solaris SPARC and x86 based systems and other third-party vendors. | <i>Solaris Hardware Compatibility List for x86 Platforms</i> |

Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Typographic Conventions

The following table describes the typographic conventions that are used in this book.

TABLE P-2 Typographic Conventions

| Typeface | Description | Example |
|------------------|---|---|
| AaBbCc123 | The names of commands, files, and directories, and onscreen computer output | Edit your <code>.login</code> file. Use <code>ls -a</code> to list all files. <code>machine_name% you have mail.</code> |
| AaBbCc123 | What you type, contrasted with onscreen computer output | <code>machine_name% su</code> Password: |
| <i>aabbcc123</i> | Placeholder: replace with a real name or value | The command to remove a file is <code>rm filename</code> . |
| <i>AaBbCc123</i> | Book titles, new terms, and terms to be emphasized | Read Chapter 6 in the <i>User's Guide</i> . <i>A cache</i> is a copy that is stored locally. Do <i>not</i> save the file. Note: Some emphasized items appear bold online. |

Shell Prompts in Command Examples

The following table shows the default UNIX system prompt and superuser prompt for shells that are included in the Oracle Solaris OS. Note that the default system prompt that is displayed in command examples varies, depending on the Oracle Solaris release.

TABLE P-3 Shell Prompts

| Shell | Prompt |
|--|--------|
| Bash shell, Korn shell, and Bourne shell | \$ |

TABLE P-3 Shell Prompts (Continued)

| Shell | Prompt |
|--|---------------|
| Bash shell, Korn shell, and Bourne shell for superuser | # |
| C shell | machine_name% |
| C shell for superuser | machine_name# |

Platform Conventions

The following keyboard and mouse conventions are applicable to SPARC and x86 based systems:

- The key referred to as Return is labeled Enter on some keyboards.
- From left to right on a three-button mouse, the default settings for CDE are SELECT, ADJUST, and MENU. For example, the text says, “Click SELECT” instead of “Click the left mouse button.” Otherwise, these keys are referred to as mouse button 1, mouse button 2, and mouse button 3.
- From left to right on a two-button mouse, the default settings are SELECT and MENU. The ADJUST function is obtained by simultaneously pressing SELECT and the Shift key on the keyboard (Shift-SELECT).

Planning for a Oracle Solaris Installation From CD or DVD Media (Tasks)

This book describes how to use CD or DVD media to install the Oracle Solaris operating system (OS) on a nonnetworked system. You can install either a UFS-based file system or a ZFS-based root pool.

Note – This chapter provides planning information for installing a UFS root (/) file system and some planning information for a ZFS root pool.

- For more planning information for an installation of a ZFS root pool, see [Chapter 6, “ZFS Root File System Installation \(Planning\),”](#) in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*.
 - If you want to install a ZFS root pool, see [Chapter 3, “Installing With the Oracle Solaris Interactive Text Installer for ZFS Root Pools \(Planning and Tasks\).”](#)
-

This chapter describes the preparations for completing a successful installation, including the sections described below. The following chapter describes each step in an installation for SPARC systems and an installation for x86 systems.

- [“System Requirements and Recommendations” on page 10](#)
This section describes system requirements to install the Oracle Solaris OS. General guidelines for planning the disk space are also provided.
- [“Checklist for Installation” on page 17](#)
This section contains a checklist to help you gather all of the information that you need to install your system.
- [“Where to Find Additional Installation Information” on page 28](#)

Note – This book uses the term *slice*, but some Oracle Solaris documentation and programs might refer to a slice as a partition. To avoid confusion, this book distinguishes between `fdisk` partitions (which are supported only in Oracle Solaris for x86 based systems) and the divisions within the `fdisk` partition, which might be called slices or partitions.

System Requirements and Recommendations

The following tables list basic system requirements to install the Oracle Solaris OS.

TABLE 1-1 Memory, Swap, and Processor Recommendations

| Requirement | Size |
|------------------------------|--|
| Memory to install or upgrade | <ul style="list-style-type: none"> ■ For UFS file systems, the memory requirements are as follows. For SPARC systems: <ul style="list-style-type: none"> ■ 1.5 GB is the minimum memory required. ■ 1.5 GB or greater is the recommended memory. For x86 systems: <ul style="list-style-type: none"> ■ 1.5 GB is the minimum memory required. ■ 1.5 GB or greater is the recommended memory. <p>Note – Some optional installation features are enabled only when sufficient memory is present. For example, if you install from a DVD with insufficient memory, you install through the Oracle Solaris installation program's text installer, not through the GUI. For more information about these memory requirements, see Table 1-2.</p> <ul style="list-style-type: none"> ■ In previous Oracle Solaris releases, you could not install and boot the Oracle Solaris OS from a disk that was greater than 1 TB in size. Starting with the Oracle Solaris 10 10/09 release, you can install and boot the Oracle Solaris OS from a disk that is up to 2 TB in size. Starting with the Oracle Solaris 10 10/09 release, you can use the VTOC label on a disk of any size, but the addressable space by the VTOC is limited to 2 TB. This feature allows disks that are larger than 2 TB to be used as boot drives, but the usable space from the label is limited to 2 TB. Note – This feature is only available on systems that run a 64-bit kernel. A minimum of 1.5 GB of memory is required for x86 based systems. For detailed information, see “Two-Terabyte Disk Support for Installing and Booting the Oracle Solaris OS” in <i>System Administration Guide: Devices and File Systems</i>. ■ For ZFS root pools in SPARC and x86 systems: <ul style="list-style-type: none"> ■ 1.5 GB is the minimum memory. ■ 1.5 GB of memory is recommended for overall ZFS performance. ■ At least 16 GB of disk space is recommended. |
| Swap area | <ul style="list-style-type: none"> ■ For UFS file systems, 512 MB is the default size ■ For ZFS root pools, see “Disk Space Requirements for a ZFS Installation” in <i>Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade</i> <p>Note – You might need to customize the swap space. Swap space is based on the size of the system's hard disk.</p> |
| Processor requirements | <ul style="list-style-type: none"> ■ For SPARC based systems: 200-MHz or faster processor is required. ■ For x86 based systems: 120-MHz or faster processor is recommended. Hardware floating-point support is required. |

Oracle Solaris Installation Program GUI or Text Installer Requirements

The Oracle Solaris installation program on the Oracle Solaris Operating System DVD or Oracle Solaris Software - 1 CD can be run with a graphical user interface (GUI) or as an interactive text installer in a desktop or console session. For x86 based systems, the Solaris Device Configuration Assistant is included in the Oracle Solaris installation program.

- GUI – The Oracle Solaris installation GUI provides windows, pull-down menus, buttons, scrollbars, and iconic images to enable you to interact with the installation program. The GUI requires a local or remote DVD-ROM or CD-ROM drive or network connection, video adapter, keyboard, monitor, and enough memory. For more information about these memory requirements, see [Table 1–2](#).
- Text installer – The Oracle Solaris interactive text installer enables you to type information in a terminal or console window to interact with the installation program. You can run the text installer in a desktop session with a windowing environment, or in a console session. The text installer requires a local or remote DVD-ROM or CD-ROM drive or network connection, keyboard, and monitor. You can run the Oracle Solaris installation text installer with the `tip` command. For more information, see the man page, [tip\(1\)](#).

You can choose to install the software with a GUI or with or without a windowing environment. If there is sufficient memory, the GUI is displayed by default. Other environments are displayed by default if memory is insufficient for the GUI. You can override defaults with the `nowin` or `text` boot options. But, you are limited by the amount of memory in your system or by installing remotely. Also if the Oracle Solaris installation program does not detect a video adapter, it automatically displays in a console-based environment. [Table 1–2](#) describes these environments and list memory requirements for displaying them.

TABLE 1–2 Memory Requirements for Display Options

| Memory | Type of Installation | Description |
|-------------------|----------------------|---|
| 1.5 GB or greater | Text-based | Contains no graphics, but provides a window and the ability to open other windows. If you install by using the <code>text</code> boot option and the system has enough memory, you are installing in a windowing environment. If you are installing remotely through a <code>tip</code> line or using the <code>nowin</code> boot option, you are limited to the console-based installation. |
| 1.5 GB or greater | GUI-based | Provides windows, pull-down menus, buttons, scrollbars, and iconic images. |

You can also specify the installer you want to use during the installation by entering a selection or special command at a prompt. For instructions, see the procedures in [Chapter 2, “Installing With the Oracle Solaris Installation Program For UFS File Systems \(Tasks\)”](#).

General Disk Space Planning and Recommendations

Planning disk space is different for everyone. Consider allocating space for the following conditions, depending on your needs.

TABLE 1-3 General Disk Space and Swap Space Planning

| Conditions for Space Allocations | Description |
|---|---|
| For UFS file systems | <p>For each file system that you create, allocate an additional 30 percent more disk space than you need to enable you to upgrade to future Oracle Solaris versions.</p> <p>By default, the Oracle Solaris installation methods create only root (/) and /swap. When space is allocated for OS services, the /export directory is also created. If you are upgrading to a major Oracle Solaris release, you might need to reslice your system or allocate double the space that you need at installation time. If you are upgrading to an update, you could prevent having to reslice your system by allocating extra disk space for future upgrades. An Oracle Solaris update release needs approximately 10 percent more disk space than the previous release. You can allocate an additional 30 percent of disk space for each file system to allow space for several Oracle Solaris updates.</p> <p>Note – In previous Oracle Solaris releases, you could not install and boot the Oracle Solaris OS from a disk that was greater than 1 TB in size. Starting with the Oracle Solaris 10 10/09 release, you can install and boot the Oracle Solaris OS from a disk that is up to 2 TB in size.</p> <p>Starting with the Oracle Solaris 10 10/09 release, you can use the VTOC label on a disk of any size, but the addressable space by the VTOC is limited to 2 TB. This feature allows disks that are larger than 2 TB to be used as boot drives, but the usable space from the label is limited to 2 TB.</p> <p>This feature is only available on systems that run a 64-bit kernel. A minimum of 1.5 GB of memory is required for x86 based systems.</p> <p>For detailed information, see “Two-Terabyte Disk Support for Installing and Booting the Oracle Solaris OS” in <i>System Administration Guide: Devices and File Systems</i>.</p> |
| The /var file system for UFS file systems | <p>If you intend to use the crash dump feature <code>savecore(1M)</code>, allocate double the amount of your physical memory in the /var file system.</p> |

TABLE 1-3 General Disk Space and Swap Space Planning (Continued)

| Conditions for Space Allocations | Description |
|--|---|
| Swap | <p>Note – For swap allocations for a ZFS root pool, see “Disk Space Requirements for a ZFS Installation” in <i>Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade</i>. For a UFS file system, the Oracle Solaris installation program allocates a default swap area of 512 MB under the following conditions:</p> <ul style="list-style-type: none"> ■ If you use the installation program’s automatic layout of disk slices ■ If you avoid manually changing the size of the swap slice <p>By default, the Oracle Solaris installation programs allocate swap space by placing swap so that it starts at the first available disk cylinder (typically cylinder 0 on SPARC based systems). This placement provides maximum space for the root (/) file system during the default disk layout and enables the growth of the root (/) file system during an upgrade.</p> <p>If you think you might need to expand the swap area in the future, you can place the swap slice so that it starts at another disk cylinder by using one of the following methods.</p> <ul style="list-style-type: none"> ■ For the Oracle Solaris installation program, you can customize the disk layout in cylinder mode and manually assign the swap slice to the desired location. ■ For the custom JumpStart installation program, you can assign the swap slice in the profile file. For more information about the JumpStart profile file, see “Creating a Profile” in <i>Oracle Solaris 10 8/11 Installation Guide: Custom JumpStart and Advanced Installations</i>. <p>For an overview of the swap space, see Chapter 19, “Configuring Additional Swap Space (Tasks),” in <i>System Administration Guide: Devices and File Systems</i>.</p> |
| A server that is providing home directory file systems | By default, home directories are usually located in the /export file system. |
| The Oracle Solaris software group you are installing | A software group is a grouping of software packages. When you are planning disk space, remember that you can add or remove individual software packages from the software group that you select. For information about software groups, see “Disk Space Recommendations for Software Groups” on page 15. |
| Upgrade | <ul style="list-style-type: none"> ■ If you are using Live Upgrade, a feature of Oracle Solaris, to upgrade an inactive boot environment and want information about disk space planning, see “Live Upgrade Disk Space Requirements” in <i>Oracle Solaris 10 8/11 Installation Guide: Live Upgrade and Upgrade Planning</i> ■ If you are using other Oracle Solaris installation methods to plan disk space, see “Upgrading With Disk Space Reallocation” in <i>Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade</i>. |
| Language support | For example, Chinese, Japanese, or Korean. If you plan to install a single language, allocate approximately 0.7 GB of additional disk space for the language. If you plan to install all language supports, you need to allocate up to approximately 2.5 GB of additional disk space for the language supports, depending on the software group you install. |
| Printing or mail support | Allocate additional space. |

TABLE 1-3 General Disk Space and Swap Space Planning (Continued)

| Conditions for Space Allocations | Description |
|---|----------------------------|
| Additional software or third-party software | Allocate additional space. |

Disk Space Recommendations for Software Groups

The Oracle Solaris software groups are collections of Oracle Solaris packages. Each software group includes support for different functions and hardware drivers.

- For an initial installation, you select the software group to install, based on the functions that you want to perform on the system.
- For an upgrade, you must upgrade to a software group that is installed on the system. For example, if you previously installed the End User Oracle Solaris Software Group on your system, you cannot use the upgrade option to upgrade to the Developer Oracle Solaris Software Group. However, during the upgrade you can add software to the system that is not part of the currently installed software group.

When you are installing the Oracle Solaris software, you can choose to add or remove packages from the Oracle Solaris software group that you selected. When you are selecting which packages to add or remove, you need to know about software dependencies and how the Oracle Solaris software is packaged.

The following figure shows the grouping of software packages. Reduced Network Support contains the minimal number of packages and Entire Oracle Solaris Software Group Plus OEM Support contains all the packages.

FIGURE 1-1 Oracle Solaris Software Groups




Table 1-4 lists the Oracle Solaris software groups and the recommended amount of disk space that you need to install each group.

Note – The disk space recommendations in Table 1-4 include space for the following items.

- Swap space
- Patches
- Additional software packages

You might find that the software groups require less disk space than the amount that is listed in this table.

For additional information about how to plan your disk space, see “Allocating Disk and Swap Space” in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*.

TABLE 1-4 Disk Space Recommendations for Software Groups

| Software Group | Description | Recommended Disk Space |
|---|--|------------------------|
| Entire Oracle Solaris Software Group Plus OEM Support | Contains the packages for the Entire Oracle Solaris Software Group plus additional hardware drivers, including drivers for hardware that is not on the system at the time of installation. | 8575 MB |

TABLE 1-4 Disk Space Recommendations for Software Groups (Continued)

| Software Group | Description | Recommended Disk Space |
|---|---|------------------------|
| Entire Oracle Solaris Software Group | Contains the packages for the Developer Oracle Solaris Software Group and additional software that is needed for servers. | 8529 MB |
| Developer Oracle Solaris Software Group | Contains the packages for the End User Oracle Solaris Software Group plus additional support for software development. The additional software development support includes libraries, include files, man pages, and programming tools. Compilers are not included. | 8336 MB |
| End User Oracle Solaris Software Group | Contains the packages that provide the minimum code that is required to boot and run a networked Oracle Solaris system and the Common Desktop Environment. | 7074 MB |
| Core System Support Software Group | Contains the packages that provide the minimum code that is required to boot and run a networked Oracle Solaris system. | 3093 MB |
| Reduced Network Support Software Group | Contains the packages that provide the minimum code that is required to boot and run a Oracle Solaris system with limited network service support. The Reduced Network Support Software Group provides a multiuser text-based console and system administration utilities. This software group also enables the system to recognize network interfaces, but does not activate network services. | 3035 MB |

Checklist for Installation

Use the following checklist to gather the information that you need to install the Oracle Solaris OS. You do not need to gather all of the information that is requested on the checklist. You only need to collect the information that applies to your system.

Use this checklist if you are performing an initial installation. If you are upgrading your system, see “[Checklist for Upgrading](#)” in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*.

Note – If you have a system that contains non-global zones, Live Upgrade, a feature of Oracle Solaris, is the recommended upgrade program or program to add patches. Other upgrade programs might require extensive upgrade time, because the time required to complete the upgrade increases linearly with the number of installed non-global zones.

For information about upgrading with Live Upgrade, a feature of Oracle Solaris, see [Part I, “Upgrading With Live Upgrade,”](#) in *Oracle Solaris 10 8/11 Installation Guide: Live Upgrade and Upgrade Planning*.

TABLE 1-5 Installation Checklist

| Information for Installation | Description or Example | Answer — Defaults are noted with an asterisk (*) |
|------------------------------|---------------------------------------|--|
| Network connection | Is the system connected to a network? | Networked/Nonnetworked |

TABLE 1-5 Installation Checklist (Continued)

| Information for Installation | Description or Example | Answer — Defaults are noted with an asterisk (*) |
|--|---|--|
| Credentials and proxy information for Auto Registration, a feature of Oracle Solaris | <p>Do you want to provide your support credentials and proxy information for Auto Registration with Oracle?</p> <p>Oracle Solaris Auto Registration is new in the Oracle Solaris 10 9/10 release. When you install or upgrade your system, configuration data about your system is, on rebooting, automatically communicated through the existing service tag technology to the Oracle Product Registration System. This service tag data about your system is used, for example, to help Oracle enhance customer support and services. You can learn about service tags at http://www.oracle.com/technetwork/server-storage/solaris/oracle-service-tag-faq-418684.html.</p> <p>You can use this same configuration data to create and manage your own inventory of your systems. By registering with your support credentials using one of the registration options below, you have a straightforward way to inventory your systems by recording and tracking the service tags for the systems and for the software products installed on the systems. For instructions about tracking your registered products, see http://wikis.sun.com/display/SunInventory/Sun+Inventory.</p> <p>Prior to an installation or upgrade, you can add an <code>auto_reg</code> keyword to your <code>sysidcfg</code> file to configure your Auto Registration preferences as follows:</p> <ul style="list-style-type: none"> ■ Provide your support credentials and proxy information for Auto Registration. ■ Set up an anonymous registration so that the configuration data sent to Oracle has no link to the name of a customer. ■ Disable Auto Registration so that no configuration data is sent to Oracle. <p>For instructions, see “<code>auto_reg</code> Keyword” in <i>Oracle Solaris 10 8/11 Installation Guide: Network-Based Installations</i>.</p> <p>If you do not preset the <code>auto_reg</code> keyword in the <code>sysidcfg</code> file, then during the interactive installation or upgrade, the installer asks you to provide your support credentials, or to register anonymously. If you do not provide your support credentials, the system is registered as an anonymous system. You are, also, asked to provide proxy information, if needed.</p> <p>Alternately, you can disable Auto Registration at the end of the installation or upgrade prior to rebooting. See the disabling instructions included as part of the installation procedures in this guide.</p> | <p>My Oracle Support user name and password</p> <p>Proxy server host name and port number</p> <p>HTTP proxy user name and password</p> |

TABLE 1-5 Installation Checklist (Continued)

| Information for Installation | Description or Example | Answer — Defaults are noted with an asterisk (*) |
|------------------------------|---|--|
| Network security | <p>Starting with the Solaris 10 11/06 release, you have the option during an initial installation to change the network security settings so that all network services, except Secure Shell, are disabled or restricted to respond to local requests only. This security option is only available during an initial installation, not during an upgrade. An upgrade maintains any previously set services. If necessary, you can restrict network services after an upgrade by using the <code>net services</code> command.</p> <p>During the installation, you can select restricted network security. Or, you can enable a larger set of services as in previous Oracle Solaris releases. You can safely select the restricted network security option, as any services can be individually enabled after installation. For further information about these options, see “Planning Network Security” in <i>Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade</i>.</p> <p>The network services can be enabled after installation by using the <code>net services open</code> command or by enabling individual services by using SMF commands. See “Revising Security Settings After Installation” in <i>Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade</i>.</p> | Restricted/Open network security |
| DHCP | <p>Can the system use Dynamic Host Configuration Protocol (DHCP) to configure its network interfaces?</p> <p>DHCP provides the network parameters that are necessary for installation.</p> | Yes/No* |

TABLE 1-5 Installation Checklist (Continued)

| Information for Installation | | Description or Example | Answer — Defaults are noted with an asterisk (*) |
|--|------------|--|--|
| If you are not using DHCP, note the network address. | IP Address | <p>If you are not using DHCP, supply the IP address for the system.</p> <p>Example: 172.31.255.255</p> <p>To find this information on a running system, type the following command.</p> <pre># ypmatch host-name hosts</pre> | |
| | Subnet | <p>If you are not using DHCP, is the system part of a subnet?</p> <p>If yes, what is the netmask of the subnet?</p> <p>Example: 255.255.255.0</p> <p>To find this information on a running system, type the following command.</p> <pre># more /etc/netmasks</pre> | |
| | IPv6 | <p>Do you want to enable IPv6 on this machine?</p> <p>IPv6 is a part of the TCP/IP Internet protocol that facilitates IP addressing by adding better security and increasing Internet addresses.</p> | Yes/No* |
| Host Name | | <p>Host name that you choose for the system.</p> <p>To find this information on a running system, type the following command.</p> <pre># uname -n</pre> | |
| Kerberos | | <p>Do you want to configure Kerberos security on this machine?</p> <p>If yes, gather this information:</p> <p style="text-align: right;">Default Realm:</p> <p style="text-align: right;">Administration Server:</p> <p style="text-align: right;">First KDC:</p> <p style="text-align: right;">(Optional) Additional KDCs:</p> <p>The Kerberos service is a client-server architecture that provides secure transactions over networks.</p> | Yes/No* |

TABLE 1-5 Installation Checklist (Continued)

| Information for Installation | | Description or Example | Answer — Defaults are noted with an asterisk (*) |
|---|----------------|--|--|
| If the system uses a naming service, provide the following information. | Naming Service | <p>Which naming service should this system use?</p> <p>To find this information on a running system, type the following command.</p> <pre># cat /etc/nsswitch.conf</pre> <p>A naming service stores information in a central place, which enables users, machines, and applications to communicate across the network. Examples of information that is stored are host names and addresses or user names and passwords.</p> | NIS+ /NIS /DNS /LDAP /None |
| | Domain Name | <p>Provide the name of the domain in which the system resides.</p> <p>During installation, you can choose the default NFSv4 domain name. Or, you can specify a custom NFSv4 domain name.</p> <p>For instructions about how to find the domain name on a running system, see “Checking for the NFS Version 4 Domain” in <i>System Administration Guide: Network Services</i>.</p> <p>For more information about specifying a domain name, see “NFSv4 Domain Name Configurable During Installation” in <i>Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade</i>. To preconfigure the NFSv4 domain name in the <code>sysidcfg</code> file, see “nfs4_domain Keyword” in <i>Oracle Solaris 10 8/11 Installation Guide: Network-Based Installations</i>.</p> | |

TABLE 1-5 Installation Checklist (Continued)

| Information for Installation | Description or Example | Answer — Defaults are noted with an asterisk (*) |
|------------------------------|--|--|
| | <p>NIS+ and NIS</p> <p>Do you want to specify a name server or let the installation program find one?</p> <p>If you want to specify a name server, provide the following information.</p> <p style="text-align: right;">Server's host name:</p> <ul style="list-style-type: none"> ■ For NIS clients, type the following command to display the server's host name. # ypwhich ■ For NIS+ clients, type the following command to display the server's host name. # nisping <p style="text-align: right;">Server's IP Address:</p> <ul style="list-style-type: none"> ■ For NIS clients, type the following command to display the server's IP address. # ypmatch nameserver-name hosts ■ For NIS+ clients, type the following command to display the server's IP address. # nismatch nameserver-name hosts.org_dir <p>Network Information Service (NIS) makes network administration more manageable by providing centralized control over a variety of network information, such as machine names and addresses.</p> | Specify One/Find One* |

TABLE 1-5 Installation Checklist (Continued)

| Information for Installation | Description or Example | Answer — Defaults are noted with an asterisk (*) |
|------------------------------|---|--|
| DNS | <p>Provide IP addresses for the DNS server. You must enter at least one IP address, but you can enter up to three addresses.</p> <p style="text-align: right;">Server's IP Address:</p> <p>To display the server's IP address, type the following command.</p> <p># getent hosts dns</p> <p>You can enter a list of domains to search when a DNS query is made.</p> <p style="text-align: right;">List of domains to be searched:</p> <p>The domain name system (DNS) is the naming service that the Internet provides for TCP/IP networks. DNS provides host names to the IP address service. DNS simplifies communication by using machine names instead of numerical IP addresses. DNS also serves as a database for mail administration.</p> | |
| LDAP | <p>Provide the following information about your LDAP profile.</p> <p style="text-align: right;">Profile Name:</p> <p style="text-align: right;">Profile Server:</p> <p>If you specify a proxy credential level in your LDAP profile, gather this information.</p> <p style="text-align: right;">Proxy-bind distinguished name:</p> <p style="text-align: right;">Proxy-bind password:</p> <p>Lightweight Directory Access Protocol (LDAP) defines a relatively simple protocol for updating and searching directories that are running over TCP/IP.</p> | |

TABLE 1-5 Installation Checklist (Continued)

| Information for Installation | Description or Example | Answer — Defaults are noted with an asterisk (*) |
|------------------------------|---|---|
| Default Route | <p>Do you want to specify a default route IP address or let the Oracle Solaris installation program find one?</p> <p>The default route provides a bridge that forwards traffic between two physical networks. An IP address is a unique number that identifies each host on a network.</p> <p>You have the following choices:</p> <ul style="list-style-type: none"> ■ You can specify the IP address. An <code>/etc/defaultrouter</code> file is created with the specified IP address. When the system is rebooted, the specified IP address becomes the default route. ■ You can let the Oracle Solaris installation program detect an IP address. However, the system must be on a subnet that has a router that advertises itself by using the ICMP router discovery protocol. If you are using the command-line interface, the software detects an IP address when the system is booted. ■ You can choose None if you do not have a router or do not want the software to detect an IP address at this time. The software automatically tries to detect an IP address on reboot. | Detect one*/Specify one/None |
| Time Zone | How do you want to specify your default time zone? | Geographic region* Offset from GMT Time zone file |
| Root Password | Provide the root password for the system. | |
| Keyboard | <p>If the keyboard is self-identifying, the keyboard language and layout automatically configures during installation. If the keyboard is not self-identifying, you can select from a list of supported keyboard layouts during installation.</p> <p>PS/2 keyboards are not self-identifying. You will be asked to select the keyboard layout during the installation.</p> <p>SPARC only – Previously, all of keyboards that were not self-identifying always configured for the U.S. English layout during installation.</p> <p>For further information, see “keyboard Keyword” in <i>Oracle Solaris 10 8/11 Installation Guide: Network-Based Installations</i>.</p> | |
| Locales | For which geographic regions do you want to install support? | |

TABLE 1-5 Installation Checklist (Continued)

| Information for Installation | Description or Example | Answer — Defaults are noted with an asterisk (*) |
|---|---|---|
| SPARC: Power Management (only available on SPARC systems that support Power Management) | Do you want to use Power Management? Note – If your system has Energy Star version 3 or later, you are not prompted for this information. | Yes*/No |
| Automatic reboot or CD/DVD ejection | Reboot automatically after software installation? Eject CD/DVD automatically after software installation? | Yes*/No Yes*/No |
| Default or Custom Install | Do you want to perform a default installation, or customize the installation? <ul style="list-style-type: none"> ■ Select Default installation to format the entire hard disk and install a preselected set of software. ■ Select Custom installation to modify the hard disk layout and select the software that you want to install. Note – The text installer does not prompt you to select a Default or Custom Installation. To perform a default installation, accept the default values that are provided in the text installer. To perform a custom installation, edit the values in the text installer screens. | Default installation*/Custom installation |
| Software Group | Which Oracle Solaris Software Group do you want to install? | Entire Plus OEM Entire* Developer End User Core Reduced Networking |
| Custom Package Selection | Do you want to add or remove software packages from the Oracle Solaris Software Group that you install? Note – When you select which packages to add or remove, you need to know about software dependencies and how Oracle Solaris software is packaged. | |
| Select Disks | On which disks do you want to install the Oracle Solaris software? Example: c0t0d0 | |

TABLE 1-5 Installation Checklist (Continued)

| Information for Installation | Description or Example | Answer — Defaults are noted with an asterisk (*) |
|--|--|--|
| x86: fdisk partitioning | <p>Do you want to create, delete, or modify a fdisk partition?</p> <p>Each disk that is selected for file system layout must have a fdisk partition in Oracle Solaris.</p> <p>If your system currently has a service partition, the Oracle Solaris installation program preserves the service partition by default. If you do not want to preserve the service partition, you must customize the fdisk partitions. For more information about preserving a service partition, see “Default Boot-Disk Partition Layout Preserves the Service Partition” in <i>Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade</i>.</p> <p style="text-align: right;">Select Disks for fdisk Partition Customization?</p> <p style="text-align: right;">Customize fdisk partitions?</p> | <p>Yes/No*</p> <p>Yes/No*</p> |
| Preserve Data | <p>Do you want to preserve any data that exists on the disks where you are installing the Oracle Solaris software?</p> | <p>Yes/No*</p> |
| Auto-layout File Systems | <p>Do you want the installation program to automatically lay out file systems on your disks?</p> <p>If yes, which file systems should be used for auto-layout?</p> <p>Example: /, /opt, /var</p> <p>If no, you must provide file system configuration information.</p> <p>Note – The Oracle Solaris installation GUI lays out file systems automatically by default.</p> | <p>Yes*/No</p> |
| Mount Remote File Systems | <p>Does this system need to access software on another file system?</p> <p>If yes, provide the following information about the remote file system.</p> <p style="text-align: right;">Server:</p> <p style="text-align: right;">IP Address:</p> <p style="text-align: right;">Remote File System:</p> <p style="text-align: right;">Local Mount Point:</p> | <p>Yes/No*</p> |
| If you are installing through a tip line, follow these instructions. | <p>Ensure that your window display is at least 80 columns wide and 24 rows long. For more information, see tip(1).</p> <p>To determine the current dimensions of your tip window, use the <code>stty</code> command. For more information, see the man page, stty(1).</p> | |

TABLE 1-5 Installation Checklist (Continued)

| Information for Installation | Description or Example | Answer — Defaults are noted with an asterisk (*) |
|---|--|--|
| Check your Ethernet connection. | If the system is part of a network, verify that an Ethernet connector or similar network adapter is connected to your system. | |
| Review the planning chapter and other relevant documentation. | <ul style="list-style-type: none"> ■ Review the entire planning chapter or specific sections in Part I, “Overall Planning of Any Oracle Solaris Installation or Upgrade,” in <i>Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade</i>. ■ Review the <i>Oracle Solaris 10 8/11 Release Notes</i> on http://www.oracle.com/technetwork/indexes/documentation/index.html and vendor release notes to ensure that the software you use is supported in the new Oracle Solaris release. ■ Review the <i>Oracle Solaris 10 8/11 Sun Hardware Platform Guide</i> to ensure that your hardware is supported. ■ Review the documentation that accompanied your system to ensure that your system and devices are supported by the Oracle Solaris release. | |

Where to Find Additional Installation Information

For additional information about requirements and recommendations for installing the Oracle Solaris OS, see the following sections in the *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*. This document provides system requirements and high-level planning information, such as planning guidelines for file systems and upgrade planning.

TABLE 1-6 Installation References

| Topic | Reference |
|---|--|
| New installation features | Chapter 2, “What’s New in Oracle Solaris Installation,” in <i>Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade</i> |
| Network security planning | “Planning Network Security” in <i>Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade</i> |
| Disk space guidelines and recommendations | “Allocating Disk and Swap Space” in <i>Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade</i> |

TABLE 1-6 Installation References (Continued)

| Topic | Reference |
|---|--|
| Additional requirements and recommendations for upgrading to the Oracle Solaris OS | <p>“Upgrade Planning” in <i>Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade</i></p> <p>“Checklist for Upgrading” in <i>Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade</i></p> |
| Information about working with x86 partitions during your installation | <p>“Partitioning Recommendations” in <i>Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade</i></p> |
| Information about ZFS installations, GRUB based booting, Oracle Solaris Zones partitioning technology, and RAID-1 volumes that can be created at installation | <p>Part II, “Understanding Installations That Relate to ZFS, Booting, Oracle Solaris Zones, and RAID-1 Volumes,” in <i>Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade</i></p> |
| Road map of the overall installation process | <p>“Task Map: Installing or Upgrading the Oracle Solaris Software” in <i>Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade</i></p> |

Installing With the Oracle Solaris Installation Program For UFS File Systems (Tasks)

This chapter explains how to use the Oracle Solaris installation program on the Oracle Solaris Operating System DVD or Oracle Solaris Software - 1 CD to install or upgrade Oracle Solaris software.

Note – This chapter provides installation instructions for a UFS (/) root file system. If you want to install a ZFS root pool, see [Chapter 3, “Installing With the Oracle Solaris Interactive Text Installer for ZFS Root Pools \(Planning and Tasks\).”](#)

This chapter contains the following topics:

- “SPARC: Performing an Installation or Upgrade With the Oracle Solaris Installation Program for UFS File Systems” on page 31
- “x86: Performing an Installation or Upgrade With the Oracle Solaris Installation Program for UFS File Systems” on page 45

For information about new installation features, see [Chapter 2, “What’s New in Oracle Solaris Installation,”](#) in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*. For information about all the new features in the Oracle Solaris OS, see *Oracle Solaris 10 8/11 What’s New*.

SPARC: Performing an Installation or Upgrade With the Oracle Solaris Installation Program for UFS File Systems

For UFS file systems, you can either install or upgrade the Oracle Solaris OS by using the Oracle Solaris installation program. This section lists the tasks you need to perform to install the Oracle Solaris OS, and provides detailed instructions about how to install the Oracle Solaris OS from DVD or CD media.

▼ SPARC: To Install or Upgrade With the Oracle Solaris Installation Program

This procedure describes how to install a standalone SPARC based system from CD or DVD media for UFS file systems.

Note – If you want to install the Oracle Solaris OS on a machine or domain that does not have a directly attached DVD-ROM or CD-ROM drive, you can use a DVD-ROM or CD-ROM drive that is attached to another machine. For detailed instructions, refer to [Appendix B, “Installing or Upgrading Remotely \(Tasks\),”](#) in *Oracle Solaris 10 8/11 Installation Guide: Network-Based Installations*.

Before You Begin Perform the following tasks before you begin your installation.

- Ensure that you have the necessary media.

Select one of the following options:

- For a DVD installation, you need the Oracle Solaris Operating System for SPARC Platforms DVD.
- For a CD installation:

You need the following media:

- Oracle Solaris Software CDs.
- Oracle Solaris Languages for SPARC Platforms CDs – The installation program prompts you for these CDs if necessary to support languages for specific geographic regions.

Note – Starting with the Oracle Solaris 10 9/10 release, only a DVD is provided. Oracle Solaris Software CDs are no longer provided.

- Verify that your system meets the minimum requirements.

Your system should meet the following requirements.

- Memory – 1.5 GB or greater
- Disk space – 6.8 GB or greater
- Processor speed – 200 MHz or greater

For detailed information about system requirements, see [“System Requirements and Recommendations”](#) on page 10.

- Gather the information you need to install the Oracle Solaris OS.

Select one of the following options:

- For a nonnetworked system:

Gather the following information.

- Host name of the system that you are installing
 - Language and locales that you intend to use on the system
- For a networked system, gather the following information.
-

Note – Starting with the Solaris 10 11/06 release, you have the option during an initial installation to change the network security settings so that all network services, except Secure Shell, are disabled or restricted to respond to local requests only. This security option is only available during an initial installation, not during an upgrade. An upgrade maintains any previously set services. If necessary, you can restrict network services after an upgrade by using the `netservices` command. See [“Planning Network Security” in Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade](#).

The network services can be enabled after installation by using the `netservices open` or by enabling individual services by using SMF commands. See [“Revising Security Settings After Installation” in Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade](#).

- Host name of the system that you are installing
 - Keyboard layout
-

Note – If the keyboard is self-identifying, the keyboard layout automatically configures during installation. If the keyboard is not self-identifying, you can select from a list of supported keyboard layouts during installation.

PS/2 keyboards are not self-identifying. You will be asked to select the keyboard layout during the installation.

For further information, see [“keyboard Keyword” in Oracle Solaris 10 8/11 Installation Guide: Network-Based Installations](#).

- Language and locales that you intend to use on the system
- Host IP address
- Subnet mask
- Type of naming service (for example, DNS, NIS, or NIS+)
- Domain name

Note – During installation, you can choose the default NFSv4 domain name. Or, you can specify a custom NFSv4 domain name. For further information, see “[NFSv4 Domain Name Configurable During Installation](#)” in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*.

- Host name of the name server
- Host IP address of the name server
- Root password

For information that you need to gather to install your system, see “[Checklist for Installation](#)” on page 17. If you are upgrading your system, see “[Checklist for Upgrading](#)” in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*. Note that you may need to provide your support credentials and proxy information during the installation or upgrade for Auto Registration, a feature of Oracle Solaris, as described in the checklists.

Note – If you have a system that contains non-global zones, Live Upgrade, a feature of Oracle Solaris, is the recommended upgrade program or program to add patches. Other upgrade programs might require extensive upgrade time, because the time required to complete the upgrade increases linearly with the number of installed non-global zones.

For information about upgrading with Live Upgrade, a feature of Oracle Solaris, see [Part I, “Upgrading With Live Upgrade,”](#) in *Oracle Solaris 10 8/11 Installation Guide: Live Upgrade and Upgrade Planning*.

- (Optional) Back up your system.

If you want to preserve any existing data or applications, back up the system. For detailed instructions about how to back up your system, see [Chapter 22, “Backing Up and Restoring UFS File Systems \(Overview\),”](#) in *System Administration Guide: Devices and File Systems*.

- 1 Insert the Oracle Solaris Operating System for SPARC Platforms DVD or Oracle Solaris Software for SPARC Platforms - 1 CD.**

- 2 Boot the system.**

- **If the system is new, out-of-the-box, turn on the system.**
- **If you want to install a system that is currently running, shut down the system.**

The ok prompt is displayed.

3 Start the Oracle Solaris installation program.

- To boot from the local DVD or CD and start the Oracle Solaris installation GUI in a desktop session, type the following command.

```
ok boot cdrom
```

- To boot from the local DVD or CD and start the text installer in a desktop session, type the following command.

```
ok boot cdrom - text
```

text Specifies to run the text installer in a desktop session. Use this option to override the default GUI installer.

- To boot from the local DVD or CD and start the text installer in a console session, type the following command.

```
ok boot cdrom - nowin
```

nowin Specifies to run the text installer in a console session. Use this option to override the default GUI installer.

For detailed information about the Oracle Solaris installation GUI and text installer, see [“Oracle Solaris Installation Program GUI or Text Installer Requirements” on page 12](#).

If the operating system cannot locate a self-identifying keyboard, the next screen displays keyboard layout selections.

Note – PS/2 keyboards are not self-identifying. You will be asked to select the keyboard layout during the installation.

4 (Optional) Select the desired keyboard layout from the screen below and press F2 to continue.

Configure Keyboard Layout

```
+-----+
| Please specify the keyboard layout from the list below. |
|                                                         |
| To make a selection, use the arrow keys to highlight the option and |
| press Return to mark it [X]. |
|                                                         |
|           Keyboard Layout |
|           ----- |
| [ ] Serbia-And Montenegro |
| [ ] Slovenian |
| [ ] Slovakian |
| [ ] Spanish |
| [ ] Swedish |
| [ ] Swiss-French |
| [ ] Swiss-German |
| [ ] Taiwanese |
| [ ] TurkishQ |
| [ ] TurkishF |
+-----+
```

```

|         [ ] UK-English
|         [ X] US-English
|
|         F2_Continue      F6_Help
+-----+

```

The system configures the devices and interfaces and searches for configuration files. If you selected a GUI installation in the earlier steps, the next two screens confirm GUI functioning.

5 (Optional) In the following screen, press Enter.

Starting Oracle Solaris Interactive (graphical user interface) Installation

```

+-----+
| You must respond to the first question within 30 seconds
| or the installer proceeds in a non-window environment
| (console mode).
|
| If the screen becomes blank or unreadable the installer
| proceeds in console mode.
|
| If the screen does not properly revert to console mode,
| restart the installation and make the following selection:
|
|         Solaris Interactive Text (Console session)
+-----+


```

Note – If your system has insufficient memory to display a graphical user interface (GUI), the program exists and displays an error message. You can upgrade your memory and restart the installation.

For an alternative that requires less memory to install, restart the installation and select a text installer option instead of the GUI installer option.


After progress messages are completed, another confirmation screen is displayed.

6 (Optional) Move your cursor into the following text screen and press Enter.



A list of language choices is displayed.

- 7 In the following screen, select the language you want to use during the installation, and press Enter.**



- 8 If you are prompted, answer the system configuration questions.**

- If you preconfigured all of the system information, the installation program does not prompt you to enter any configuration information. See [Chapter 2, “Preconfiguring System Configuration Information \(Tasks\)”](#), in *Oracle Solaris 10 8/11 Installation Guide: Network-Based Installations* for more information.
- If you did not preconfigure all the system information, the installation program prompts you for this information on several screens. Use the [“Checklist for Installation”](#) on [page 17](#) to help you answer the configuration questions.
- During installation, you can choose the default NFSv4 domain name. Or, you can specify a custom NFSv4 domain name. For more information about specifying a domain name, see [“NFSv4 Domain Name Configurable During Installation”](#) in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*.
- One configuration question asks you whether you want to enable network services for use by remote clients. The default response is “Yes, I would like to enable network services for use by remote clients.”

Selecting “No” provides a more secure configuration in which Secure Shell is the only network service provided to remote clients. Selecting “Yes” enables a larger set of services as in previous Oracle Solaris releases. You can safely select “No” as any services can be enabled after installation. For further information about these options, see [“Planning Network Security”](#) in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*.

The network services can be enabled after installation by using the `net services open` command or by enabling individual services by using SMF commands. See [“Revising Security Settings After Installation”](#) in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*.

- 9 After you answer the configuration questions, the Welcome to Oracle Solaris screen appears. Click Next.**

The Installer Questions screen appears.

- 10 Decide if you want to reboot the system automatically and if you want to automatically eject the disc. Click Next.**

Important: If you intend to disable Auto Registration after installation, deselect the automatic reboot.

The Specify Media screen appears.

- 11 Specify the media you are using to install. Click Next.**

The License panel appears.

- 12 Accept the license agreement to continue the installation. Click Next.**

The Oracle Solaris installation program then determines if the system can be upgraded. To upgrade, the system must have an existing Oracle Solaris root (/) file system. The Oracle Solaris installation program detects the necessary conditions and then upgrades the system.

The Select Upgrade or Initial Install screen appears.

- 13 Decide if you want to perform an initial installation or an upgrade. Click Next.**

The next screen enables you to choose a default installation or a custom installation.

- 14 Select the type of installation you want to perform. Click Next.**

- **Select Default Install to install the Entire Oracle Solaris Software Group.**
- **Select Custom Install if you want to perform the following tasks.**
 - Install a specific software group
 - Install additional software
 - Install specific software packages
 - Install a specific locale
 - Customize the disk layout

For more information about software groups, see [“Disk Space Recommendations for Software Groups”](#) on page 15.

Note – The text installer does not prompt you to select a Default or Custom Installation. To perform a default installation, accept the default values that are provided in the text installer. To perform a custom installation, edit the values in the text installer screens.

- 15 If you are prompted, answer any additional configuration questions.**

- **If you had set up your Auto Registration preferences using the `auto_reg` keyword in the `sysidcfg` file prior to the installation or upgrade, the installer does not prompt you for that information as part of completing the configuration questions.**

Note – For information about Auto Registration, see “Oracle Solaris Auto Registration” in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*.


- If you did not include the `auto_reg` keyword in the `sysidcfg` file, the installer prompts you to provide Auto Registration information as part of completing the configuration questions.

Note – If you intend to disable Auto Registration at the end of the installation or upgrade, you can proceed through these Auto Registration screens without providing any information.

- a. Choose to either register using your support credentials or to have data sent anonymously.


The GUI screen is displayed. Select or deselect registering with your credentials. Click Next to continue.

FIGURE 2-1 GUI Auto Registration Screen



Alternately, the text installer screen displays.

FIGURE 2-2 Text Auto Registration Screen



In the text screen, use the arrow keys to navigate to the option box. Press Return to mark the option box to select registering with your support credentials. Press the Esc_2 key to continue.

- b. Provide the requested proxy and credential information.

FIGURE 2-3 GUI Auto Registration Data Entry Screen

Oracle Solaris Auto Registration

To register, complete the following fields:

- Confirm your existing My Oracle Support Information.
- If using a proxy server, provide the proxy settings.

For information about what configuration data is communicated and how to control this facility, see the Release Notes or www.oracle.com/goto/solarisautoreg.

My Oracle Support User Name:

My Oracle Support Password:

Proxy Server Host Name:

Proxy Server Port Number:

HTTP Proxy User Name:

HTTP Proxy Password:


ORACLE
SOLARIS

If you chose to register in the prior screen, you are prompted to provide your My Oracle Support user name and password. If you use a proxy server, you can provide the server host name and port number, and the proxy user name and password.

If you chose an anonymous registration in the prior screen, this screen asks only for the proxy information.

Alternately, for text installs, the following screen is displayed.

FIGURE 2-4 Text Auto Registration Data Entry Screen




Use the arrow keys to navigate between lines. Type your support credentials and optional proxy entries. Press the Esc_2 key to continue.

The Ready to Install screen is displayed.

16 Review the Ready to Install screen.

Note – The GUI screen is displayed. The text install screen contains the same summary information.

FIGURE 2-5 Ready to Install Screen



- 17 **Click Install Now to install the Oracle Solaris software. Follow the instructions on the screen to install the Oracle Solaris software.**

When the Oracle Solaris installation program finishes installing the Oracle Solaris software, the system reboots automatically or prompts you to reboot manually.

If you are installing additional products, you are prompted to insert the DVD or CD for those products. For installation procedures, refer to the appropriate installation documentation.

After the installation is finished, installation logs are saved in a file. You can find the installation logs in the `/var/sadm/system/logs` and `/var/sadm/install/logs` directories.

- **If you are performing an initial installation, the installation is complete.**
- **If you are upgrading the Oracle Solaris software, you might need to correct some local modifications that were not preserved. Continue to [Step a](#).**
 - a. **Review the contents of the `/a/var/sadm/system/data/upgrade_cleanup` file to determine whether you need to correct local modifications that the Oracle Solaris installation program could not preserve.**
 - b. **Correct any local modifications that were not preserved.**

18 If you previously deselected automatic rebooting, choose one of the following two options:

- If you do not want to disable Auto Registration, eject any installation media, then manually reboot the system as follows:
`# reboot`
- If you want to disable Auto Registration so that no configuration data is sent to Oracle on reboot, perform the following steps prior to manually rebooting the system.



Caution – To disable Auto Registration using the following procedure, you must have deselected automatic reboot earlier in the installation screens.

If the system does automatically reboot, you cannot use the following steps to disable Auto Registration. Instead, after the automatic reboot, you can disable Auto Registration by using the `regadm` command. See [Chapter 17, “Working With the Oracle Solaris Auto Registration regadm Command \(Tasks\)”](#), in *System Administration Guide: Basic Administration*.

- a. When the installation is complete and before manually rebooting, open a terminal window as follows:
 - For a GUI install, right-click to open a terminal window.
 - For a text install, press “!” to open a terminal window.
- b. At the command line, remove the `/a/var/tmp/autoreg_config` file.
- c. Save the file.
- d. Eject any installation media and manually reboot the system.
`# reboot`

Troubleshooting If you encountered any problems during the installation or upgrade, see [Appendix A, “Troubleshooting \(Tasks\)”](#), in *Oracle Solaris 10 8/11 Installation Guide: Custom JumpStart and Advanced Installations*.

x86: Performing an Installation or Upgrade With the Oracle Solaris Installation Program for UFS File Systems

You can either install or upgrade the Oracle Solaris OS by using the Oracle Solaris installation program. This section lists the task you need to perform to install the Oracle Solaris OS, and provides detailed instructions about how to install the Oracle Solaris OS from DVD or CD media.

▼ x86: To Install or Upgrade With the Oracle Solaris Installation Program With GRUB

The Oracle Solaris installation programs for x86 based systems use the GRUB boot loader. This procedure describes how to install a standalone x86 based system with the GRUB bootloader from CD or DVD media for a UFS file system. For overview information about the GRUB boot loader, see [Chapter 7, “SPARC and x86 Based Booting \(Overview and Planning\),”](#) in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*.

Note – If you want to install the Oracle Solaris OS on a machine or domain that does not have a directly attached DVD-ROM or CD-ROM drive, you can use a DVD-ROM or CD-ROM drive that is attached to another machine. For detailed instructions, refer to [Appendix B, “Installing or Upgrading Remotely \(Tasks\),”](#) in *Oracle Solaris 10 8/11 Installation Guide: Network-Based Installations*.

Before You Begin Perform the following tasks before you begin your installation.

- Ensure that you have the necessary media.

Select one of the following options:

- If you are installing from a DVD, use the Oracle Solaris Operating System for x86 Platforms DVD.
- If you are installing from CD media:

You need the following media:

- Oracle Solaris Software CDs.
- Oracle Solaris Languages for x86 Platforms CDs – The installation program prompts you for these CDs if necessary to support languages for specific geographic regions.

Note – Starting with the Oracle Solaris 10 9/10 release, only a DVD is provided. Oracle Solaris Software CDs are no longer provided.

- Check your system BIOS to make sure you can boot from CD or DVD media.
- Acquire any install time updates (ITUs) or drivers that you need to install the Oracle Solaris OS on your hardware. To determine if you need an ITU or additional drivers, see your hardware documentation.
- Verify that your system meets the minimum requirements.

Your system should meet the following requirements.

- Memory – 1.5 GB or greater
- Disk space – 6.8 GB or greater
- Processor speed – 120 MHz or greater with hardware floating point

For detailed information about system requirements, see “[System Requirements and Recommendations](#)” on page 10.

If you are installing the Oracle Solaris OS on a system that is not produced by Oracle Corporation, check the Oracle Solaris Hardware Compatibility List at <http://www.oracle.com/webfolder/technetwork/hcl/index.html> before you begin to install.

- Gather the information you need to install the Oracle Solaris OS.
 - For a nonnetworked system:

You need the following information:

- Host name of the system that you are installing
 - Language and locales that you intend to use on the system
- For a networked system, gather the following information.

Note – Starting with the Solaris 10 11/06 release, you have the option during an initial installation to change the network security settings so that all network services, except Secure Shell, are disabled or restricted to respond to local requests only. This security option is only available during an initial installation, not during an upgrade. An upgrade maintains any previously set services. If necessary, you can restrict network services after an upgrade by using the `net services` command. See “[Planning Network Security](#)” in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*.

The network services can be enabled after installation by using the `net services open` command or by enabling individual services by using SMF commands. See “[Revising Security Settings After Installation](#)” in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*.

- Host name of the system that you are installing
- Keyboard layout

Note – If the keyboard is self-identifying, the keyboard layout automatically configures during installation. If the keyboard is not self-identifying, you can select from a list of supported keyboard layouts during installation.

For further information, see “[keyboard Keyword](#)” in *Oracle Solaris 10 8/11 Installation Guide: Network-Based Installations*.

- Language and locales that you intend to use on the system
- Host IP address
- Subnet mask
- Type of naming service (for example, DNS, NIS, or NIS+)
- Domain name

Note – During installation, you can choose the default NFSv4 domain name. Or, you can specify a custom NFSv4 domain name. For more information about specifying a domain name, see “[NFSv4 Domain Name Configurable During Installation](#)” in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*.

- Host name of the name server
- Host IP address of the name server
- Root password

For information that you need to gather to install your system, see “[Checklist for Installation](#)” on page 17. If you are upgrading your system, see “[Checklist for Upgrading](#)” in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*. Note that you may need to provide your support credentials and proxy information during the installation or upgrade for Auto Registration, as described in the checklists.

Note – If you have a system that contains non-global zones, Live Upgrade, a feature of Oracle Solaris, is the recommended upgrade program or program to add patches. Other upgrade programs might require extensive upgrade time, because the time required to complete the upgrade increases linearly with the number of installed non-global zones.

For information about upgrading with Live Upgrade, a feature of Oracle Solaris, see [Part I, “Upgrading With Live Upgrade,”](#) in *Oracle Solaris 10 8/11 Installation Guide: Live Upgrade and Upgrade Planning*.

- (Optional) Back up your system.

If you want to preserve any existing data or applications, back up the system. For detailed instructions about how to back up your system, see [Chapter 22, “Backing Up and Restoring UFS File Systems \(Overview\),”](#) in *System Administration Guide: Devices and File Systems*.

1 Insert the appropriate media in your system.

If you boot from the Oracle Solaris Operating System DVD or the Oracle Solaris Software - 1 CD, insert the disc. Your system’s BIOS must support booting from a DVD or CD.

You might need to manually set your BIOS to boot from a DVD or CD. See your hardware documentation for more information about how to set the BIOS.

2 Boot the system by shutting it down and then turning it off and on.

3 If you need to manually set the BIOS to boot from CD or DVD, type the appropriate key sequence to interrupt your system boot process.

Modify the boot priority in the BIOS, and exit the BIOS to return to the installation program.

A memory test and hardware detection are executed. The screen refreshes. The GRUB menu is displayed.

```
GNU GRUB version 0.95 (631K lower / 2095488K upper memory)
```

```
+-----+
| Solaris                               |
| Solaris Serial Console ttya           |
| Solaris Serial Console ttyb (for lx50, v60x and v65x) |
|                                       |
+-----+
```

Use the ^ and v keys to select which entry is highlighted.
Press enter to boot the selected OS, 'e' to edit the

commands before booting, or 'c' for a command-line.

4 Select the appropriate installation option.

- **If you want to install the Oracle Solaris OS from CD or DVD on your current system, select Oracle Solaris, then press Enter.**

Select this option if you want to install the system by using the default values.

- **If you want to install the Oracle Solaris OS and send the screen output to serial console ttya (COM1), select Oracle Solaris Serial Console ttya.**

Select this option if you want to change the system display to a device that is connected to serial port COM1.

- **If you want to install the Oracle Solaris OS and send the screen output to serial console ttyb (COM2), select Oracle Solaris Serial Console ttyb.**

Select this option if you want to change the system display to a device that is connected to serial port COM2.

- **If you want to install the Oracle Solaris OS with specific boot arguments, follow these steps.**

You might want to use specific boot arguments to customize the system configuration during the installation.

- a. **On the GRUB menu, select the installation option you want to edit, then press e.**

Boot commands that are similar to the following text are displayed in the GRUB menu.

```
kernel /boot/multiboot kernel/unix -B install_media=cdr0m
module /boot/x86.miniroot
```

- b. **Use the arrow keys to select the boot entry that you want to edit, then press e.**

The boot command that you want to edit is displayed in the GRUB edit window.

- c. **Edit the command by typing the boot arguments or options you want to use.**

The command syntax for the Grub edit menu is as follows.

```
grub edit>kernel /boot/multiboot kernel/unix/ \
install [url|ask] -B options install_media=media_type
```

```
grub edit>kernel$ /boot/platform/i86pc/$ISADIR/kernel/unix/ \
install [url|ask] -B options install_media=media_type
```

For information about boot arguments and command syntax, see [Chapter 9, “Installing From the Network \(Command Reference\)”](#), in *Oracle Solaris 10 8/11 Installation Guide: Network-Based Installations*.

d. To go back to the GRUB menu, select one of the following alternatives.

- **To go back to the GRUB menu and save your edits, press Enter.**
The GRUB menu is displayed. The edits you made to the boot command are displayed.
- **To go back to the GRUB menu without saving your edits, press Escape.**
The original GRUB menu is displayed.

e. To begin the installation, type b in the GRUB menu.

The Oracle Solaris installation program checks the default boot disk for the requirements to install or upgrade the system. If the Oracle Solaris installation cannot detect the system configuration, the program prompts you for any missing information.

When the check is completed, the installation selection screen is displayed.

5 Select an installation type.

The installation selection screen displays the following options.

Select the type of installation you want to perform:

```
1 Solaris Interactive
2 Custom JumpStart
3 Solaris Interactive Text (Desktop session)
4 Solaris Interactive Text (Console session)
5 Apply driver updates
6 Single user shell
```

Enter the number of your choice followed by the <ENTER> key.
Alternatively, enter custom boot arguments directly.

If you wait 30 seconds without typing anything,
an interactive installation will be started.

- **To install the Oracle Solaris OS, choose from the following options.**
 - **To install with the Oracle Solaris interactive installation GUI, type 1, then press Enter.**
 - **To perform an unattended custom JumpStart installation, type 2, then press Enter.**
For information about JumpStart installations, see [Oracle Solaris 10 8/11 Installation Guide: Custom JumpStart and Advanced Installations](#).
 - **To install with the interactive text installer in a desktop session, type 3, then press Enter. You can also type b - text at the prompt.**
Select this installation type to override the default GUI installer and run the text installer.

For detailed information about the Oracle Solaris installation GUI and text installer, see “[System Requirements and Recommendations](#)” on page 10.

- **To install with the interactive text installer in a console session, type 4, then press Enter. You can also type `b - nowin` at the prompt.**

Select this installation type to override the default GUI installer and run the text installer.

The system configures the devices and interfaces, and searches for configuration files. If the operating system cannot locate a self-identifying keyboard, the next screen displays keyboard layout selections. If the system locates a self-identifying keyboard, skip to [Step 9](#).

Note – To perform system administration tasks before your installation, choose one of the two options described below, instead of selecting one of the previously-described installation options.

- To update drivers or install an install time update (ITU), insert the update media, type 5, then press Enter.
You might need to update drivers or install an ITU to enable the Oracle Solaris OS to run on your system. Follow the instructions for your driver update or ITU to install the update.
- To perform system administration tasks, type 6, then press Enter.
You might want to launch a single user shell if you need to perform any system administration tasks on your system before you install. For information about system administration tasks you can perform prior to installation, see [System Administration Guide: Basic Administration](#).

After you perform these system administration tasks, the previous list of options is displayed. Select the appropriate option to continue the installation.

6 (Optional) Select the desired keyboard layout from the screen below and press F2 to continue.

Configure Keyboard Layout

```
+-----+
| Please specify the keyboard layout from the list below. |
|                                                         |
| To make a selection, use the arrow keys to highlight the option and |
| press Return to mark it [X]. |
|                                                         |
|           Keyboard Layout |
|           ----- |
| [ ] Serbia-And Montenegro |
| [ ] Slovenian |
| [ ] Slovakian |
| [ ] Spanish |
| [ ] Swedish |
| [ ] Swiss-French |
| [ ] Swiss-German |
| [ ] Taiwanese |
|                                                         |
+-----+
```

```

|         [ ] TurkishQ
|         [ ] TurkishF
|         [ ] UK-English
|         [ X] US-English
|
|     F2_Continue      F6_Help
+-----+

```

The system configures the devices and interfaces and searches for configuration files. If you selected a GUI installation in the earlier steps, the next two screens confirm GUI functioning.

7 (Optional) In the following screen, press Enter.

Starting Oracle Solaris Interactive (graphical user interface) Installation

```

+-----+
| You must respond to the first question within 30 seconds
| or the installer proceeds in a non-window environment
| (console mode).
|
| If the screen becomes blank or unreadable the installer
| proceeds in console mode.
|
| If the screen does not properly revert to console mode,
| restart the installation and make the following selection:
|
|         Solaris Interactive Text (Console session)
+-----+


```

Note – If your system has insufficient memory, the program exists and displays an error message. You can upgrade your memory and restart the installation.

For an alternative that requires less memory to install, restart the installation and select a text installer option instead of a GUI installer option.


After progress messages are completed, another confirmation screen is displayed.

8 (Optional) Move your cursor into the following text screen and press Enter.



A list of language choices is displayed.

- 9 In the following screen, select the language you want to use during the installation, and press Enter.



- 10 If you are prompted, answer any remaining configuration questions.

- If you preconfigured all of the system information, the installation program does not prompt you to enter any configuration information. See [Chapter 2, “Preconfiguring System Configuration Information \(Tasks\)”](#), in *Oracle Solaris 10 8/11 Installation Guide: Network-Based Installations* for more information.
- If you did not preconfigure all the system information, the installation program prompts you for this information on several screens. Use the “[Checklist for Installation](#)” on [page 17](#) to help you answer the configuration questions.
- One configuration question asks you whether you want to enable network services for use by remote clients. The default response is “Yes, I would like to enable network services for use by remote clients.”

Selecting “No” provides a more secure configuration in which Secure Shell is the only network service provided to remote clients. Selecting “Yes” enables a larger set of services as in previous Oracle Solaris releases. You can safely select “No” as any services can be enabled after installation. For further information about these options, see “[Planning Network Security](#)” in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*.

The network services can be enabled after installation by using the `net services open` command or by enabling individual services by using SMF commands. See “[Revising Security Settings After Installation](#)” in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*.

After you answer the configuration questions, the Welcome to Oracle Solaris panel appears.

- 11 Click Next in the Welcome screen.

The Installer Questions screen displays.

- 12 Decide if you want to reboot the system automatically and if you want to automatically eject the disc. Click Next.

Important: If you intend to disable Auto Registration after installation, deselect the automatic reboot.

The Specify Media screen appears.

13 Specify the media you are using to install. Click Next.

The License screen appears.

14 Accept the license agreement to continue the installation. Click Next.

The Oracle Solaris installation program then determines if the system can be upgraded. To upgrade, the system must have an existing Oracle Solaris root (/) file system. The Oracle Solaris installation program detects the necessary conditions and then upgrades the system.

The Select Upgrade or Initial Install screen appears.

15 Decide if you want to perform an initial installation or an upgrade. Click Next.

Note – If you restored the diagnostic or service partition on your system before you started the installation, you might not be able to upgrade to the Oracle Solaris OS. For more information, see [“Service Partition Not Created by Default on Systems With No Existing Service Partition” in Oracle Solaris 10 8/11 Installation Guide: Live Upgrade and Upgrade Planning](#).

The next screen enables you to choose a default installation or a custom installation.

16 Select the type of installation you want to perform. Click Next.

- **Select Default Install to install the Entire Oracle Solaris Software Group.**
- **Select Custom Install if you want to perform the following tasks.**
 - Install a specific software group
 - Install additional software
 - Install specific software packages
 - Install a specific locale
 - Customize the disk layout

For more information about software groups, see [“Disk Space Recommendations for Software Groups” on page 15](#). For information about customizing fdisk partitions, see [“Partitioning Recommendations” in Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade](#).

Note – The text installer does not prompt you to select a Default or Custom Installation. To perform a default installation, accept the default values that are provided in the text installer. To perform a custom installation, edit the values in the text installer screens.

17 If you are prompted, answer any additional configuration questions.

- **If you had set up your Auto Registration preferences using the `auto_reg` keyword in the `sysidcfg` file prior to the installation or upgrade, the installer does not prompt you for that information as part of completing the configuration questions.**

Note – For information about Auto Registration, see “Oracle Solaris Auto Registration” in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*.


- **If you did not include the `auto_reg` keyword in the `sysidcfg` file, the installer prompts you to provide Auto Registration information as part of completing the configuration questions.**

Note – If you intend to disable Auto Registration at the end of the installation or upgrade, you can proceed through these Auto Registration screens without entering any information.

- Choose to either register using your support credentials or to have data sent anonymously.**


The GUI screen is displayed. Select or deselect registering with your credentials. Click Next to continue.

FIGURE 2-6 GUI Auto Registration Screen



Alternately, the text installer screen displays.

FIGURE 2-7 Text Auto Registration Screen



In the text screen, use the arrow keys to navigate to the option box. Press Return to mark the option box to select registering with your support credentials. Press the Esc_2 key to continue.

b. Provide the requested proxy and credential information.

FIGURE 2-8 GUI Auto Registration Data Entry Screen

Oracle Solaris Auto Registration

To register, complete the following fields:

- Confirm your existing My Oracle Support Information.
- If using a proxy server, provide the proxy settings.

For information about what configuration data is communicated and how to control this facility, see the Release Notes or www.oracle.com/goto/solarisautoreg.

My Oracle Support User Name:

My Oracle Support Password:

Proxy Server Host Name:

Proxy Server Port Number:

HTTP Proxy User Name:


HTTP Proxy Password:

If you chose to register in the prior screen, you are prompted to provide your My Oracle Support user name and password. If you use a proxy server, you can provide the server host name and port number, and the proxy user name and password.

If you chose an anonymous registration in the prior screen, this screen asks only for the proxy information.

Alternately, for text installs, the following screen is displayed.

FIGURE 2-9 Text Auto Registration Data Entry Screen




Use the arrow keys to navigate between lines. Type your support credentials and optional proxy entries. Press the Esc_2 key to continue.

The Ready to Install screen is displayed.

18 Review the Ready to Install screen.

Note – The GUI screen is shown here. The text version of this screen contains the same information.

FIGURE 2-10 Oracle Solaris Installation Ready to Install Screen



- 19 Click Install Now to install the Oracle Solaris software. Follow the instructions on the screen to install the Oracle Solaris software and any additional software on the system.**

When the Oracle Solaris installation program is finished installing the Oracle Solaris software, the system reboots automatically or prompts you to reboot manually.

After the installation is finished, installation logs are saved in a file. You can find the installation logs in the `/var/sadm/system/logs` and `/var/sadm/install/logs` directories

- **If you are performing an initial installation, the installation is complete. If you deselected automatic reboot, continue to [Step 20](#).**
- **If you are upgrading the Oracle Solaris software, you might need to correct some local modifications that were not preserved. Go to [Step a](#).**
 - a. **Review the contents of the `/a/var/sadm/system/data/upgrade_cleanup` file to determine whether you need to correct local modifications that the Oracle Solaris installation program could not preserve.**
 - b. **Correct any local modifications that were not preserved.**

20 If you previously deselected automatic rebooting, choose one of the following two options:

- **If you do not want to disable Auto Registration, eject any installation media, then manually reboot the system as follows:**

```
# reboot
```
- **If you want to disable Auto Registration so that no configuration data is sent to Oracle on reboot, perform the following steps prior to manually rebooting the system.**



Caution – To disable Auto Registration using the following procedure, you must have deselected automatic reboot earlier in the installation screens.

If the system does automatically reboot, you cannot use the following steps to disable Auto Registration. Instead, after the automatic reboot, you can disable Auto Registration by using the `regadm` command. See [Chapter 17, “Working With the Oracle Solaris Auto Registration `regadm` Command \(Tasks\),” in *System Administration Guide: Basic Administration*](#).

a. When the installation is complete and before manually rebooting, open a terminal window as follows:

- **For a GUI install, right-click to open a terminal window.**
- **For a text install, press “!” to open a terminal window.**

b. At the command line, remove the `/a/var/tmp/autoreg_config` file.

c. Save the file.

d. Eject any installation media and manually reboot the system.

```
# reboot
```

After the system reboots, a GRUB menu lists the operating systems that are installed, including the newly installed Oracle Solaris OS.

e. Select which operating system you want to boot.

The default selection loads if you do not make another selection.

More Information Next Steps

If you install multiple operating systems on your machine, you need to instruct the GRUB boot loader to recognize these operating systems in order to boot. For more information, see [“Modifying Boot Behavior by Editing the GRUB Menu at Boot Time” in *System Administration Guide: Basic Administration*](#).

Troubleshooting If you encounter any problems during the installation or upgrade, see [Appendix A](#), “Troubleshooting (Tasks),” in *Oracle Solaris 10 8/11 Installation Guide: Custom JumpStart and Advanced Installations*.

Installing With the Oracle Solaris Interactive Text Installer for ZFS Root Pools (Planning and Tasks)

This chapter explains how to use the Oracle Solaris interactive installation program on the Oracle Solaris Operating System DVD or Oracle Solaris Software - 1 CD to perform an initial installation of a ZFS root pool.

This chapter contains the following topics:

- “ZFS Root Pool Installation (Planning)” on page 63
- “Performing Initial Installation With the Oracle Solaris Interactive Text Installer for ZFS” on page 65

ZFS Root Pool Installation (Planning)

You can perform an initial installation by using the Oracle Solaris interactive text installer to create a ZFS storage pool that contains a bootable ZFS root pool. You cannot use the standard GUI installation program to install a ZFS root pool.

The Solaris interactive text installation process is similar to previous Oracle Solaris releases. The difference is that you have the option to install a UFS (*/*) root file system or ZFS root pool. UFS is still the default file system. You must select the ZFS option, to create and install a ZFS storage pool.

If you already have ZFS storage pools on the system, they remain untouched, unless you select the disks in the existing pool to create the new storage pool. If you have an existing ZFS storage pool that you want to use for your ZFS root file system, you must use Live Upgrade, a feature of Oracle Solaris, to migrate your existing UFS root (*/*) file system to a ZFS root pool. Live Upgrade also provides the means to upgrade a ZFS root pool. For more information, see Chapter 11, “Live Upgrade and ZFS (Overview),” in *Oracle Solaris 10 8/11 Installation Guide: Live Upgrade and Upgrade Planning*.

Before you begin the initial installation to create a ZFS storage pool, see Chapter 6, “ZFS Root File System Installation (Planning),” in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*.

Note – Installations to ZFS root file systems for both SPARC and x86 systems require a minimum of at least 1.5 GB or greater memory.

What's New in the Oracle Solaris 10 8/11 Release

Starting with the Oracle Solaris 10 8/11 release, you can use the interactive text-based installation method to install a Flash archive to a ZFS root pool.

For detailed instructions and limitations, see [Chapter 5, “Installing and Booting an Oracle Solaris ZFS Root File System,”](#) in *Oracle Solaris ZFS Administration Guide*.

Unlike the ZFS Flash archives in the previous releases, a Flash archive created on a ZFS root master system does not contain all the existing boot environments. Instead, the archive only contains the active ZFS boot environment. The archive does not include those datasets that are excluded explicitly with the `-D` option of the `lucreate` command and the user data present in the top-level pool dataset. The swap and dump volumes are not included into the archive but are created when the Flash archive is installed.

For more information on creating and installing ZFS Flash archives, refer to [Chapter 5, “Installing and Booting an Oracle Solaris ZFS Root File System,”](#) in *Oracle Solaris ZFS Administration Guide*.

What's New in the Solaris 10 10/09 Release

Starting with the Oracle Solaris 10 10/09 release, you can set up a JumpStart profile to identify a Flash archive of a ZFS root pool.

A Flash archive can be created on a system that is running a UFS root file system or a ZFS root file system. A Flash archive of a ZFS root pool contains the entire pool hierarchy, except for the swap and dump volumes, and any excluded datasets. The swap and dump volumes are created when the Flash archive is installed.

You can use the Flash archive installation method as follows:

- Generate a Flash archive that can be used to install and boot a system with a ZFS root file system.
- Perform a JumpStart installation of a system by using a ZFS Flash archive.

For detailed instructions and limitations, see [“Installing a ZFS Root File System \(Oracle Solaris Flash Archive Installation\)”](#) in *Oracle Solaris ZFS Administration Guide*.

Performing Initial Installation With the Oracle Solaris Interactive Text Installer for ZFS

This procedure describes how to install a standalone SPARC based system from CD or DVD media.

▼ SPARC: How to Install a ZFS Root Pool

Before You Begin If you want to install the Oracle Solaris OS on a machine or domain that does not have a directly attached DVD-ROM or CD-ROM drive, you can use a drive that is attached to another machine. For detailed instructions, refer to [Appendix B, “Installing or Upgrading Remotely \(Tasks\)”](#), in *Oracle Solaris 10 8/11 Installation Guide: Network-Based Installations*.

Ensure that you have the necessary media.

- For a DVD installation, you need the Oracle Solaris Operating System for SPARC Platforms DVD.
- For a CD installation:

You need the following media:

- Oracle Solaris Software CDs.
- Oracle Solaris Languages for SPARC Platforms CDs – The installation program prompts you for these CDs if necessary to support languages for specific geographic regions.

Note – Starting with the Oracle Solaris 10 8/11 release, only a DVD is provided. Oracle Solaris Software CDs are no longer provided.

If you want to preserve any existing data or applications, back up the system.

- For backing up a UFS file system, see [Chapter 22, “Backing Up and Restoring UFS File Systems \(Overview\)”](#), in *System Administration Guide: Devices and File Systems*
- For backing up a ZFS root pool, see “[Sending and Receiving ZFS Data](#)” in *Oracle Solaris ZFS Administration Guide*

- 1 **Insert the Oracle Solaris Operating System for SPARC Platforms DVD or Oracle Solaris Software for SPARC Platforms - 1 CD.**
- 2 **Boot the system.**
 - **If the system is new, just removed from its packaging, turn on the system.**
 - **If you want to install a system that is currently running, shut down the system.**

The ok prompt is displayed.

- 3 **Start the Oracle Solaris interactive text installer. You cannot run the installation GUI to install a ZFS root pool. To boot from the local DVD or CD and start the text installer in a desktop session, type the following command:**

```
ok boot cdrom - text
```

text Specifies to run the text installer in a desktop session. Use this option to override the default GUI installer.

If the operating system cannot locate a self-identifying keyboard, the next screen displays keyboard layout selections.

Note – PS/2 keyboards are not self-identifying. You will be asked to select the keyboard layout during the installation.

- 4 **(Optional) Select the desired keyboard layout from the following screen and press F2 to continue.**

Configure Keyboard Layout

```
+-----+
| Please specify the keyboard layout from the list below.
|
| To make a selection, use the arrow keys to highlight the option and
| press Return to mark it [X].
|
|           Keyboard  Layout
|           -----
| [ ] Serbia-And Montenegro
| [ ] Slovenian
| [ ] Slovakian
| [ ] Spanish
| [ ] Swedish
| [ ] Swiss-French
| [ ] Swiss-German
| [ ] Taiwanese
| [ ] TurkishQ
| [ ] TurkishF
| [ ] UK-English
| [ X] US-English
|
| F2_Continue      F6_Help
+-----+
```

The system configures the devices and interfaces and searches for configuration files. A list of language choices might be displayed. If this screen is not displayed, skip to [Step 6](#).

- 5 (Optional) You might see a screen to select a language. Select the language you want to use during the installation, and press F2.

Select a Language

```
+-----+
| Please specify the the language from the list below.
|
| To make a selection, use the arrow keys to highlight the option and
| press Return to mark it [X].
|
|         [ ] English
|         [ ] French
|         [ ] German
|         [ ] Italian
|         [ ] Japanese
|         [ ] Korean
|         [ ] Simplified Chinese
|         [ ] Spanish
|         [ ] Swedish
|         [ ] Traditional Chinese
|         [ ] UK-English
|
|         F2_Continue      F6_Help
+-----+
```

- 6 Press F2 to display the Oracle Solaris Installation screen.

Answer any configuration prompts that appear.

■ **Preconfiguring system information.**

Select one of the following options:

- If you preconfigured all of the system information, the installation program does not prompt you to type any configuration information. See [Chapter 2, “Preconfiguring System Configuration Information \(Tasks\),” in *Oracle Solaris 10 8/11 Installation Guide: Network-Based Installations*](#) for more information.
- If you did not preconfigure all the system information, the installation program prompts you for this information on several screens. Use the [“Checklist for Installation” on page 17](#) to help you answer the configuration questions.

■ **Network configuration.**

One configuration question asks you whether you want to enable network services for use by remote clients. The default response is “Yes, I would like to enable network services for use by remote clients.”

Selecting “No” provides a more secure configuration in which Secure Shell is the only network service provided to remote clients. Selecting “Yes” enables a larger set of services as in previous Oracle Solaris releases. You can safely select “No,” as any services can be enabled after installation. For further information about these options, see [“Planning Network Security” in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*](#).

The network services can be enabled after installation by using the `net services` open command or by enabling individual services by using SMF commands. See “[Revising Security Settings After Installation](#)” in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*.

After you answer the configuration questions and set the root password, the Oracle Solaris Interactive Installation screen is displayed.

```
Solaris Interactive Installation
+-----+
|On the following screens, you can accept the defaults or you can customize
| how Solaris software will be installed by:
|
| - Selecting the type of Solaris software to install
| - Selecting disks to hold the software you've selected
| - Selecting unbundled products to be installed with Solaris
| - Specifying how file systems are laid out on the disks
|
|After completing these tasks, a summary of your selections
|(called a profile) will be displayed.
|
|There are two ways to install your Solaris software:
|
| - 'Standard' installs your system from a standard Solaris Distribution.
|   Selecting 'standard' allows you to choose between initial install
|   and upgrade, if your system is upgradeable.
|
| - 'Flash' installs your system from one or more Flash Archives.
|
|   F2_Standard   F4_Flash   F5_Exit   F6_Help
+-----+
```

To install a ZFS Flash archive, press F4. For step-by-step instructions on installing a ZFS Flash archive, see the *Oracle Solaris ZFS Administration Guide*.

To perform an initial installation of a ZFS root file system, press F2.

7 Decide whether you want to reboot the system automatically and whether you want to automatically eject the disc. Press F2.

Important: If you want to disable Auto Registration, a feature of Oracle Solaris, after the installation and prior to rebooting, deselect automatic rebooting.

If you already have ZFS storage pools on the system, they are acknowledged by the following message, but remain untouched, unless you select the disks in the existing pools to create the new storage pool.

There are existing ZFS pools available on this system. However, they can only be upgraded using the Live Upgrade tools. The following screens will only allow you to install a ZFS root system, not upgrade one.

Press F2 to continue when you see the message that you already have ZFS storage pools on the system.

The License screen appears.

8 Accept the license agreement to continue the installation. Press F2.

The Select Upgrade or Initial Install screen might display. If you have UFS file system that is upgradeable, this screen is displayed. If this screen does not display, skip to [Step 10](#).

9 To perform a ZFS installation, you must press F4 for an initial installation.

Screens for choosing geographic regions, locales, and additional products are displayed.

10 Make your choices for geographic regions, locales, and additional products.

The Choose a Filesystem Type screen is displayed.

11 To create a ZFS root pool, select the ZFS option and press F2.

Choose a Filesystem Type

```
+-----+
| Select the filesystem to use for your Solaris installation |
|                                                           |
|           [ ] UFS                                         |
|           [X] ZFS                                         |
|                                                           |
| F2_Continue      F6_Help                                 |
+-----+
```

The Select Software screen is displayed.

12 Select the type of installation you want to perform. Press F2.

To perform a default installation, accept the default value that is provided. To perform a custom installation, edit the values in the text installer screen. In this example screen, the default Entire Distribution Software Group is checked for installation.

For more information about software groups, see “[Disk Space Recommendations for Software Groups](#)” on page 15.

Select Software

```
+-----+
| Select the Solaris software to install on the system      |
|                                                           |
| Note: After selecting a software group, you can add or   |
| remove software by customizing it. However this         |
| requires understanding of software dependencies and how  |
| Solaris software is packaged.                            |
|                                                           |
| [ ] Entire Distribution plus OEM support .....8575.00 MB |
| [X] Entire Distribution.....8529.00 MB                  |
| [ ] Developer System Support.....8336.00 MB            |
| [ ] End User System Support.....7074.00 MB             |
| [ ] Core System Support.....3093.00 MB                  |
| [ ] Reduced Networking Core System Support.....3035.00  |
|                                                           |
| F2_Continue      F6_Help                                 |
+-----+
```

The Select Disks screen is displayed.

13 After you select the software to be installed, you are prompted to select the disks to create your ZFS storage pool. This screen is similar to previous Oracle Solaris releases, except for the following text:

For ZFS, multiple disks will be configured as mirrors, so the disk you choose, or the slice within the disk must exceed the Suggested Minimum value.

You can select the disk or disks to be used for your ZFS root pool.

- If you select a single disk and want to configure mirroring later, see the `zpool attach` command in “Managing Devices in ZFS Storage Pools” in *Oracle Solaris ZFS Administration Guide*.
- If you select two disks, a mirrored two-disk configuration is set up for your root pool. Either a two-disk or three-disk mirrored pool is optimal.
- If you have eight disks and you select all eight disks, those eight disks are used for the root pool as one big mirror. This is not an optimal configuration.

A RAID-Z pool configuration for the root pool is not supported. For more information about configuring ZFS storage pools, see “Replication Features of a ZFS Storage Pool” in *Oracle Solaris ZFS Administration Guide*.

```
Select Disks
+-----+
|On this screen you must select the disks for installing Solaris
|software. Start by looking at the Suggested Minimum Field;
|this value is the approximate space needed to install the software
|you've selected. For ZFS, multiple disks will be configured as mirrors,
|so the disk you choose on the slice within the disk must exceed
|the Suggested Minimum Value.
|
| Note: ** denotes the current boot disk
|
|Disk Device                                Available Space
|=====|
|[X]** c0t0d0                                69994 MB (F4 to edit)
|[X]  c0t1d0                                69994 MB
|[-]  c0t2d0                                 0 MB
|[-]  c0t3d0                                 0 MB
|
|                                         Maximum Root Size: 69994 MB
|                                         Suggested Minimum: 8529 MB
|
|      F2_Continue   F3_Go Back   F4_Edit   F5_Exit   F6_Help
+-----+
```

The Preserve Data screen is displayed.

14 (Optional) Preserve data on the disk where you are installing the software.

If a disk that you have selected for installing contains file systems or has unnamed slices that you want to save, you can save these file systems or unnamed slices now.

Preserve Data?

```
+-----+
|Do you want to preserve existing data? At least one of the disks you've |
|selected for installing Solaris software has file systems or unnamed slices|
|that you may want to save                                             |
|                                                                       |
|      F2_Continue      F4_Preserve      F6_Help                       |
+-----+
```

If you pressed F4 to save data, the screen for saving data is displayed.

15 (Optional) Select the data to save.

To manage a ZFS root to file system, provide the size of the entire disk in a slice. For example, provide the size in slice 0. Sharing different root file systems on the same disk can be hard to manage.

To copy data off the disk to be installed as the root file system, exit the installer and back up the data that you want to preserve on this disk, and then restart the installer.

```
# install-solaris
```

The screen for configuring ZFS settings is displayed.

16 You can accept the default values. Or, you can change the name of the ZFS pool, the dataset name, the pool size, swap and dump. In addition, you can modify the way the /var file system is created and mounted.

Configure ZFS Settings

```
+-----+
|Specify the name of the pool to be created from the disk(s) you have chosen.|
|Also specify the name of the dataset to be created within the pool that is |
|to be used as the root directory for the filesystem.                       |
|                                                                           |
|              ZFS Pool Name: rpool                                       |
|      ZFS Root Dataset Name: s10zfsBE                                    |
|              ZFS Pool Size in (MB): 69995                               |
|              Size of swap area in (MB): 2048                           |
|              Size of dump area in (MB): 1024                            |
|      (Pool size must be between 6481 MB and 69995 MB)                   |
|                                                                           |
|                                                                           |
|              [X] Keep / and /var combined                               |
|              [ ] Put /var on a separate dataset                         |
|                                                                           |
|      F2_Continue      F3_Go Back      F5_Exit      F6_Help             |
+-----+
```

The screen for mounting a remote file system is displayed.

17 Decide if you want to mount a remote file system.

```
Mount Remote File System
+-----+
|Do you want to mount a software from a remote file server? This may
|be necessary if you had to remove software because of disk space problems.
|
|      F2_Continue      F6_Help
+-----+
```

18 If you are prompted, answer any additional configuration questions.

- **If you set up your Auto Registration preferences using the `auto_reg` keyword in the `sysidcfg` file prior to the installation or upgrade, the installer does not prompt you for that information as part of completing the configuration questions.**


Note – For information about using the `auto_reg` keyword, see “[auto_reg Keyword](#)” in *Oracle Solaris 10 8/11 Installation Guide: Network-Based Installations*.

- **If you did not include the `auto_reg` keyword in the `sysidcfg` file, the installer prompts you to provide Auto Registration information as part of completing the configuration questions.**

Note – If you intend to disable Auto Registration at the end of the installation or upgrade, you can proceed through these Auto Registration screens without entering any information.

- a. **Choose to either register using your support credentials, or to have data sent anonymously.**

FIGURE 3-1 Text Auto Registration Screen




In this screen, use the arrow keys to navigate to the option box. Press Return to mark the option box to select registering with your support credentials. Press the Esc_2 key to continue.

b. Provide the requested proxy and credential information.

If you chose to register in the prior screen, you are prompted to provide your My Oracle Support user name and password. If you use a proxy server, you can provide the server host name and port number, and the proxy user name and password.

If you chose an anonymous registration in the prior screen, this screen asks only for the proxy information.

FIGURE 3-2 Text Auto Registration Data Entry Screen



In this screen, use the arrow keys to navigate between lines. Type your support credentials and optional proxy entries. Press the Esc_2 key to continue.

The Profile screen is displayed.

- 19 Review the Profile screen that displays your choices for installation. You can change the installation profile if needed. The following example is of a final installation Profile screen.

```

Profile
+-----+
|The information shown below is your profile for installing Solaris software.|
|It reflects the choices you've made on previous screens.                    |
+-----+
|
|          Installation Option: Initial
|              Boot Device: c0t0d0
|    Root File System Type: ZFS
|          Client Services: None
|              System Locale: C ( C )
|
|          Software: Solaris 10, Entire Distribution
|          Pool Name: rpool
|    Boot Environment Name: s10zfsBE
|          Pool Size: 69995 MB
|    Devices in Pool: c0t0d0
|                   c0t1d0
|
|    F2_Begin Installation    F4_Change    F5_Exit    F6_Help
+-----+
    
```

20 To install the Oracle Solaris software, press F2. Follow the instructions on the screen to install the Oracle Solaris software.

When the Oracle Solaris interactive text program finishes installing the Oracle Solaris software, the system reboots automatically or prompts you to reboot manually.

If you are installing additional products, you are prompted to insert the DVD or CD for those products. For installation procedures, refer to the appropriate installation documentation.

After the installation is finished, installation logs are saved in a file. You can find the installation logs in the `/var/sadm/system/logs` and `/var/sadm/install/logs` directories.

The installation is complete. If you deselected automatic rebooting after installation, continue to [Step 21](#).

21 If you previously deselected automatic rebooting, choose one of the following two options:

- **If you do not want to disable Auto Registration, eject any installation media, then manually reboot the system as follows:**
`reboot`
- **If you want to disable Auto Registration so that no configuration data is sent to Oracle on reboot, perform the following steps prior to manually rebooting the system.**



Caution – To disable Auto Registration using the following procedure, you must have deselected automatic reboot earlier in the installation screens.

If the system does automatically reboot, you cannot use the following steps to disable Auto Registration. Instead, after the automatic reboot, you can disable Auto Registration by using the `regadm` command. See [Chapter 17, “Working With the Oracle Solaris Auto Registration regadm Command \(Tasks\)”](#), in *System Administration Guide: Basic Administration*.

- a. **When the installation is complete and before manually rebooting, press “!” to open a terminal window.**
- b. **At the command line, remove the `/a/var/tmp/autoreg_config` file.**
- c. **Save the file.**
- d. **Eject any installation media and manually reboot the system.**

`reboot`

Your system boots to the ZFS root pool that you installed.

You can display a list of available boot environments by using the boot command with the -L option. For more information about SPARC based booting, see [“Booting From a Specified ZFS Root File System on a SPARC Based System”](#) in *System Administration Guide: Basic Administration*.

22 (Optional) You can review the resulting ZFS storage pool and file system information, as in the following example.

The sample zpool status and zfs list output identify the root pool components.

```
# zpool status
pool: rpool
state: ONLINE
scan: none requested
config:

    NAME          STATE          READ WRITE CKSUM
    rpool         ONLINE         0     0     0
    mirror-0     ONLINE         0     0     0
        c0t0d0s0  ONLINE         0     0     0
        c0t1d0s0  ONLINE         0     0     0

errors: No known data errors
# zfs list
NAME                                USED  AVAIL  REFER  MOUNTPOINT
rpool                                7.15G 59.4G   106K   /rpool
rpool/ROOT                           4.45G 59.4G   31K    legacy
rpool/ROOT/s10zfsBE                  4.45G 59.4G   4.45G  /
rpool/dump                            1.00G 59.4G   1.00G  -
rpool/export                          63K   59.4G   32K    /export
rpool/export/home                     31K   59.4G   31K    /export/home
rpool/swap                            2.06G 61.5G   16K    -
```

If you have initially created your ZFS storage pool with one disk, you can convert the disk to a mirrored ZFS configuration after the installation. For more information about adding or attaching disks, see [“Managing Devices in ZFS Storage Pools”](#) in *Oracle Solaris ZFS Administration Guide*.

Troubleshooting If you encounter any problems during the installation, see [Appendix A, “Troubleshooting \(Tasks\)”](#), in *Oracle Solaris 10 8/11 Installation Guide: Custom JumpStart and Advanced Installations*.

x86: Performing an Initial Installation With the Oracle Solaris Interactive Text Installer for ZFS

You can perform an initial installation the Oracle Solaris OS by using the Oracle Solaris interactive text installer. An initial installation overwrites the data on the disks being installed. This section provides detailed instructions about how to install the Oracle Solaris OS from DVD or CD media.

▼ x86: To Install With the Oracle Solaris Interactive Text Installer With GRUB for ZFS

The Oracle Solaris installation program for x86 based systems uses the GRUB boot loader. This procedure describes how to install a standalone x86 based system with the GRUB boot loader from CD or DVD media. For overview information about the GRUB boot loader, see “[Modifying Boot Behavior by Editing the GRUB Menu at Boot Time](#)” in *System Administration Guide: Basic Administration*.

Before You Begin Perform the following tasks before you begin your installation.

- If you want to install the Oracle Solaris OS on a machine or domain that does not have a directly attached DVD-ROM or CD-ROM drive, you can use a DVD-ROM or CD-ROM drive that is attached to another machine. For detailed instructions, refer to [Appendix B, “Installing or Upgrading Remotely \(Tasks\),”](#) in *Oracle Solaris 10 8/11 Installation Guide: Network-Based Installations*.
- Ensure that you have the necessary media.

Select one of the following options:

- If you are installing from a DVD, use the Oracle Solaris Operating System for x86 Platforms DVD.
- If you are installing from CD media:

You need the following media.

- Oracle Solaris Software CDs.
- Oracle Solaris Languages for x86 Platforms CDs – The installation program prompts you for these CDs if necessary to support languages for specific geographic regions.

Note – Starting with the Oracle Solaris 10 8/11 release, only a DVD is provided. Oracle Solaris Software CDs are no longer provided.

- Check your system BIOS to ensure you can boot from CD or DVD media.
- If you are installing the Oracle Solaris OS on a system that is not produced by Oracle Corporation, check the Oracle Solaris Hardware Compatibility List at <http://www.oracle.com/webfolder/technetwork/hcl/index.html> before you begin to install.
- (Optional) Back up your system.

If you want to preserve any existing data or applications, back up the system.

- For backing up a UFS file system, see [Chapter 22, “Backing Up and Restoring UFS File Systems \(Overview\)”](#), in *System Administration Guide: Devices and File Systems*.
- For backing up a ZFS root pool, see “Sending and Receiving ZFS Data” in *Oracle Solaris ZFS Administration Guide*.

1 Insert the appropriate media in your system.

If you boot from the Oracle Solaris Operating System DVD or the Oracle Solaris Software - 1 CD, insert the disc. Your system's BIOS must support booting from a DVD or CD.

You might need to manually set your BIOS to boot from a DVD or CD. See your hardware documentation for more information about how to set the BIOS.

2 Boot the system by shutting it down and then turning it off and on.

3 If you need to manually set the BIOS to boot from CD or DVD, type the appropriate key sequence to interrupt your system boot process.

Modify the boot priority in the BIOS, and exit the BIOS to return to the installation program.

A memory test and hardware detection are executed. The screen refreshes. The GRUB menu is displayed.

```
GNU GRUB version 0.95 (631K lower / 2095488K upper memory)
```

```
+-----+
| Solaris                               |
| Solaris Serial Console ttya           |
| Solaris Serial Console ttyb (for lx50, v60x and v65x) |
|                                       |
+-----+
```

Use the ^ and v keys to select which entry is highlighted.
Press enter to boot the selected OS, 'e' to edit the
commands before booting, or 'c' for a command-line.

4 Select Solaris, then press Enter.

The Oracle Solaris installation program checks the default boot disk for the requirements to install or upgrade the system. If the installation program cannot detect the system configuration, the program prompts you for any missing information.

When the check is completed, the installation selection screen is displayed.

5 Select an installation type. To install the Oracle Solaris OS with the interactive text installer in a desktop session, type 3, then press Enter.

Select this installation type to override the default GUI installer and run the text installer for a ZFS installation.

Select the type of installation you want to perform:

```

1 Solaris Interactive
2 Custom JumpStart
3 Solaris Interactive Text (Desktop session)
4 Solaris Interactive Text (Console session)
5 Apply driver updates
6 Single user shell

```

Enter the number of your choice followed by the <ENTER> key. Alternatively, enter custom boot arguments directly.

If you wait 30 seconds without typing anything, an interactive installation will be started.

The system configures the devices and interfaces, and searches for configuration files. If the operating system cannot locate a self-identifying keyboard, the next screen displays keyboard layout selections. If the system locates a self-identifying keyboard, skip to [Step 7](#).

6 (Optional) Select the desired keyboard layout from the following screen and press F2 to continue.

Configure Keyboard Layout

```

+-----+
| Please specify the keyboard layout from the list below. |
|                                                         |
| To make a selection, use the arrow keys to highlight the option and |
| press Return to mark it [X]. |
|                                                         |
|           Keyboard Layout |
|           ----- |
| [ ] Serbia-And Montenegro |
| [ ] Slovenian |
| [ ] Slovakian |
| [ ] Spanish |
| [ ] Swedish |
| [ ] Swiss-French |
| [ ] Swiss-German |
| [ ] Taiwanese |
| [ ] TurkishQ |
| [ ] TurkishF |
| [ ] UK-English |
| [ X] US-English |
|                                                         |
| F2_Continue      F6_Help |
+-----+

```

The system configures the devices and interfaces and searches for configuration files. You might see two screens that confirm that windows are functioning. Confirm the next two screens and continue in text mode.

7 (Optional) In the following screen, press Enter.

Starting Solaris Interactive (graphical user interface)
Installation

```
+-----+
| You must respond to the first question within 30 seconds |
| or the installer proceeds in a non-window environment   |
| (console mode).                                         |
|                                                         |
| If the screen becomes blank or unreadable the installer |
| proceeds in console mode.                               |
|                                                         |
| If the screen does not properly revert to console mode, |
| restart the installation and make the following selection:|
|                                                         |
|         Solaris Interactive Text (Console session)       |
|                                                         |
+-----+
```

After progress messages are completed, another confirmation screen is displayed.

8 (Optional) Move your cursor into the following text screen and press Enter.

```
+-----+
| If the screen is legible, press ENTER in this window.   |
|                                                         |
+-----+
```

A list of language choices might be displayed. If this screen is not displayed, skip to [Step 10](#).

9 (Optional) In the following screen, select the language you want to use during the installation, and press F2.

Select a Language

```
+-----+
| Please specify the the language from the list below.    |
|                                                         |
| To make a selection, use the arrow keys to highlight   |
| the option and press Return to mark it [X].            |
|                                                         |
|         [ ] English                                     |
|         [ ] French                                     |
|         [ ] German                                     |
|         [ ] Italian                                    |
|         [ ] Japanese                                   |
|         [ ] Korean                                     |
|         [ ] Simplified Chinese                         |
|         [ ] Spanish                                    |
|         [ ] Swedish                                    |
|         [ ] Traditional Chinese                        |
|         [ ] UK-English                                 |
|                                                         |
| F2_Continue      F6_Help                               |
+-----+
```


10 Press F2 to display the Oracle Solaris Installation screen.

Answer any configuration prompts that appear.

- **Preconfiguring system information.**

Select one of the following options:

- If you preconfigured all of the system information, the installation program does not prompt you to type any configuration information. See [Chapter 2, “Preconfiguring System Configuration Information \(Tasks\),” in *Oracle Solaris 10 8/11 Installation Guide: Network-Based Installations*](#) for more information.
- If you did not preconfigure all the system information, the installation program prompts you for this information on several screens. Use the [“Checklist for Installation” on page 17](#) to help you answer the configuration questions.

- **Network configuration.**

One configuration question asks you whether you want to enable network services for use by remote clients. The default response is “Yes, I would like to enable network services for use by remote clients.”

Selecting “No” provides a more secure configuration in which Secure Shell is the only network service provided to remote clients. Selecting “Yes” enables a larger set of services as in previous Oracle Solaris releases. You can safely select “No,” as any services can be enabled after installation. For further information about these options, see [“Planning Network Security” in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*](#).

The network services can be enabled after installation by using the `net services open` command or by enabling individual services by using SMF commands. See [“Revising Security Settings After Installation” in *Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade*](#).

After you answer the configuration questions and set the root password, the Oracle Solaris Interactive Installation screen is displayed.

```
Solaris Interactive Installation
+-----+
|On the following screens, you can accept the defaults or you can customize
| how Solaris software will be installed by:
| - Selecting the type of Solaris software to install
| - Selecting disks to hold the software you've selected
| - Selecting unbundled products to be installed with Solaris
| - Specifying how file systems are laid out on the disks
|
|After completing these tasks, a summary of your selections
|(called a profile) will be displayed.
|
|There are two ways to install your Solaris software:
|
| - 'Standard' installs your system from a standard Solaris Distribution.
|   Selecting 'standard' allows you to choose between initial install
|   and upgrade, if your system is upgradeable.
```

```

| - 'Flash' installs your system from one or more Flash Archives.
|
|   F2_Continue      F4-Flash      F5-Exit      F6_Help
+-----+

```

To install a ZFS Flash archive, press F4. For step-by-step instructions on installing a ZFS Flash archive, see *Oracle Solaris ZFS Administration Guide*.

To perform an initial installation of a ZFS root file system, press F2.

11 Decide if you want to reboot the system automatically and if you want to automatically eject the disc. Press F2.

Important: If you want to disable Auto Registration prior to rebooting the system, deselect automatic rebooting.

If you already have ZFS storage pools on the system, they are acknowledged by the following message, but remain untouched, unless you select the disks in the existing pools to create the new storage pool.

There are existing ZFS pools available on this system. However, they can only be upgraded using the Live Upgrade tools. The following screens will only allow you to install a ZFS root system, not upgrade one.

Press F2 to continue when you see the message that you already have ZFS storage pools on the system.

The License screen appears.

12 Accept the license agreement to continue the installation. Press F2.

The Select Upgrade or Initial Install screen might display. If you have UFS file system that is upgradeable, this screen is displayed. If this screen does not display, skip to [Step 14](#).

13 To perform a ZFS installation, you must press F4 for an initial installation.

Screens for choosing geographic regions, locales, and additional products are displayed.

14 Make your choices for geographic regions, locales, and additional products.

The Choose a Filesystem Type is displayed.

15 To create and install a ZFS root pool, select the ZFS option.

```

Choose a Filesystem Type
+-----+
| Select the filesystem to use for your Solaris installation
|
|           [ ] UFS
|           [X] ZFS
|
|   F2_Continue      F6_Help
+-----+

```

The Select Software screen is displayed.

16 Select the type of installation you want to perform. Press F2.

To perform a default installation, accept the default value that is provided. To perform a custom installation, edit the values in the text installer screen. In this example screen, the default Entire Distribution Software Group is checked for installation.

For more information about software groups, see [“Disk Space Recommendations for Software Groups” on page 15](#).

Select Software

```
+-----+
|Select the Solaris software to install on the system
|
|Note: After selecting a software group, you can add or remove
|software by customizing it. However this requires understanding of
|software dependencies and how Solaris software is packaged.
|
| [ ] Entire Distribution plus OEM support .....8575.00 MB
|[X] Entire Distribution.....8529.00 MB
| [ ] Developer System Support.....8336.00 MB
| [ ] End User System Support.....7074.00 MB
| [ ] Core System Support.....3093.00 MB
| [ ] Reduced Networking Core System Support.....3035.00 MB
|
|
|      F2_Continue      F6_Help
+-----+
```

The Select Disks screen is displayed.

17 After you select the software to be installed, you are prompted to select the disks to create your ZFS storage pool. This screen is similar to previous Oracle Solaris releases, except for the following text:

For ZFS, multiple disks will be configured as mirrors, so the disk you choose, or the slice within the disk must exceed the Suggested Minimum value.

You can select the disk or disks to be used for your ZFS root pool.

- If you select a single disk and want to configure mirroring later, see the `zpool attach` command in [“Managing Devices in ZFS Storage Pools” in Oracle Solaris ZFS Administration Guide](#).
- If you select two disks, a mirrored two-disk configuration is setup for your root pool. Either a two-disk or three-disk mirrored pool is optimal.
- If you have eight disks and you select all eight disks, those eight disks are used for the root pool as one big mirror. This is not an optimal configuration.

A RAID-Z pool configuration for the root pool is not supported. For more information about configuring ZFS storage pools, see “Replication Features of a ZFS Storage Pool” in *Oracle Solaris ZFS Administration Guide*.

```

Select Disks
+-----+
|On this screen you must select the disks for installing Solaris
|software. Start by looking at the Suggested Minimum Field;
|this value is the approximate space needed to install the software
|you've selected. For ZFS, multiple disks will be configured as mirrors,
|so the disk you choose on the slice within the disk must exceed
|the Suggested Minimum Value.
|
|   Note: ** denotes the current boot disk
|
|Disk Device                               Available Space
|=====|
|[X]** c0t0d0                               69994 MB (F4 to edit)
|[X]  c0t1d0                               69994 MB
|[-]  c0t2d0                                0 MB
|[-]  c0t3d0                                0 MB
|
|                                     Maximum Root Size: 69994 MB
|                                     Suggested Minimum: 8529 MB
|
|   F2_Continue   F3_Go Back   F4_Edit   F6_Help
+-----+

```

The Preserve Data screen is displayed.

18 (Optional) Preserve data on the disk where you are installing the software.

If a disk that you have selected for installing contains file systems or have unnamed slices that you want to save, you can save these file systems or unnamed slices now.

```

Preserve Data?
+-----+
|Do you want to preserve existing data? At least one of the disks you've
|selected for installing Solaris software has file systems or unnamed slices
|that you may want to save
|
|   F2_Continue   F4_Preserve   F6_Help
+-----+

```

If you pressed F4 to save data, the screen for saving data is displayed.

19 (Optional) Select the data to save.

To manage a ZFS root to file system, provide the size of the entire disk in a slice. For example, provide the size in slice 0. Sharing different root file systems on the same disk can be hard to manage.

To copy data off the disk to be installed as the root file system, exit the installer and back up the data that you want to preserve on this disk, and then restart the installer.

install-solaris

The screen for configuring ZFS settings is displayed.

- 20 You can accept the default values. Or, you can change the name of the ZFS pool, the dataset name, the pool size, swap, and dump. In addition, you can modify the way the /var file system is created and mounted.**

Configure ZFS Settings

```
+-----+
|Specify the name of the pool to be created from the disk(s) you have chosen.|
|Also specify the name of the dataset to be created within the pool that is |
|to be used as the root directory for the filesystem.                        |
|                                                                            |
|           ZFS Pool Name: rpool                                           |
|    ZFS Root Dataset Name: s10ZfsBE                                       |
|           ZFS Pool Size in (MB): 69995                                    |
|           Size of swap area in (MB): 2048                                 |
|           Size of dump area in (MB): 1024                                |
|           (Pool size must be between 6481 MB and 69995 MB)              |
|                                                                            |
|                               [X] Keep / and /var combined                |
|                               [ ] Put /var on a separate dataset          |
|                                                                            |
|    F2_Continue      F3_Go Back      F5_Exit      F6_Help                |
+-----+
```

The screen for mounting a remote file system is displayed.

- 21 Decide if you want to mount a remote file system.**

Mount Remote File System

```
+-----+
|Do you want to mount a software from a remote file server? This may       |
|be necessary if you had to remove software because of disk space problems.|
|                                                                            |
|           F2_Continue      F6_Help                                       |
+-----+
```

- 22 If you are prompted, answer any additional configuration questions.**

- If you set up your Auto Registration preferences using the `auto_reg` keyword in the `sysidcfg` file prior to the installation or upgrade, the installer does not prompt you for that information as part of completing the configuration questions.


Note – For information about Auto Registration, see [“Oracle Solaris Auto Registration” in Oracle Solaris 10 8/11 Installation Guide: Planning for Installation and Upgrade.](#)

- If you did not include the `auto_reg` keyword in the `sysidcfg` file, the installer prompts you to provide Auto Registration information as part of completing the configuration questions.

Note – If you intend to disable Auto Registration at the end of the installation or upgrade, you can proceed through these Auto Registration screens without entering any information.

- a. Choose to either register using your support credentials or to have data sent anonymously.

FIGURE 3-3 Text Auto Registration Screen



In the text screen, use the arrow keys to navigate to the option box. Press Return to mark the option box to select registering with your support credentials. Press the Esc_2 key to continue.

- b. Provide the requested proxy and credential information.

If you chose to register in the prior screen, you are prompted to provide your My Oracle Support user name and password. If you use a proxy server, you can provide the server host name and port number, and the proxy user name and password.

If you chose an anonymous registration in the prior screen, this screen asks only for the proxy information.

FIGURE 3-4 Text Auto Registration Data Entry Screen

Use the arrow keys to navigate between lines. Type your support credentials and optional proxy entries. Press the Esc_2 key to continue.

The Profile screen is displayed.

- 23 Review the Profile screen that displays your choices for installation. You can change the installation profile if needed. The following example is of a final installation Profile screen.**

```

Profile
+-----+
|The information shown below is your profile for installing Solaris software.|
|It reflects the choices you've made on previous screens.                  |
+-----+
|
|      Installation Option: Initial
|          Boot Device: c0t0d0
|      Root File System Type: ZFS
|          Client Services: None
|          System Locale: C ( C )
|
|          Software: Solaris 10, Entire Distribution
|          Pool Name: rpool
|      Boot Environment Name: s10ZfsBE
|          Pool Size: 69995 MB
|      Devices in Pool: c0t0d0
|                      c0t1d0
|
|      F2_Begin Installation   F4_Change   F5_Exit   F6_Help
+-----+

```

24 To install the Oracle Solaris software, press F2. Follow the instructions on the screen to install the Oracle Solaris software.

When the Oracle Solaris interactive text program finishes installing the Oracle Solaris software, the system reboots automatically or prompts you to reboot manually.

If you are installing additional products, you are prompted to insert the DVD or CD for those products. For installation procedures, refer to the appropriate installation documentation.

After the installation is finished, installation logs are saved in a file. You can find the installation logs in the `/var/sadm/system/logs` and `/var/sadm/install/logs` directories.

The installation is complete. If you deselected automatic reboot previously in the installer screens, continue to [Step 25](#).

25 If you previously deselected automatic rebooting, choose one of the following two options:

- **If you do not want to disable Auto Registration, eject any installation media, then manually reboot the system as follows:**

```
# reboot
```

- **If you want to disable Auto Registration so that no configuration data is sent to Oracle on reboot, perform the following steps prior to manually rebooting the system.**



Caution – To disable Auto Registration using the following procedure, you must have deselected automatic reboot earlier in the installation screens.

If the system does automatically reboot, you cannot use the following steps to disable Auto Registration. Instead, after the automatic reboot, you can disable Auto Registration by using the `regadm` command. See [Chapter 17, “Working With the Oracle Solaris Auto Registration regadm Command \(Tasks\)”](#), in *System Administration Guide: Basic Administration*.

- a. **When the installation is complete and before manually rebooting, press “!” to open a terminal window.**
- b. **At the command line, remove the `/a/var/tmp/autoreg_config` file.**
- c. **Save the file.**
- d. **Eject any installation media and manually reboot the system.**

```
# reboot
```

After the system reboots, a GRUB menu lists the operating systems that are installed, including the newly installed Oracle Solaris OS.

26 Select which operating system you want to boot.

The default selection loads if you do not make another selection.

The GRUB menu list is displayed.

```
GNU GRUB version 0.95 (637K lower / 3144640K upper memory)
+-----+
|Oracle Solaris 10 8/11 s10zfsBE|
|Solaris Failsafe              |
|                               |
+-----+
```

Use the ^ and v keys to select which entry is highlighted.
Press enter to boot the selected OS, .e. to edit the
commands before booting, or .c. for a command-line.

27 When the GRUB menu is displayed, press Enter to boot the default OS instance. The default is the newly installed root pool.

In this example, the boot environment name is szboot_0507. If you do not select an entry within 10 seconds, the system automatically boots.

28 When the installation is complete, review the resulting ZFS storage pool and file system information, as in the following example.

The sample zpool status and zfs list output identify the root pool components.

```
# zpool status
pool: rpool
state: ONLINE
scan: none requested
config:

    NAME          STATE          READ WRITE CKSUM
    rpool         ONLINE         0     0     0
    mirror-0     ONLINE         0     0     0
    c0t0d0s0     ONLINE         0     0     0
    c0t1d0s0     ONLINE         0     0     0

errors: No known data errors
# zfs list
NAME                                USED  AVAIL  REFER  MOUNTPOINT
rpool                                7.15G 59.4G   106K   /rpool
rpool/ROOT                           4.45G 59.4G   31K    legacy
rpool/ROOT/s10zfsBE                  4.45G 59.4G  4.45G   /
rpool/dump                            1.00G 59.4G  1.00G   -
rpool/export                          63K   59.4G   32K    /export
rpool/export/home                     31K   59.4G   31K    /export/home
rpool/swap                            2.06G 61.5G   16K    -
```

If you initially created your ZFS storage pool with one disk, you can convert the disk to a mirrored ZFS configuration after the installation. For more information about adding or attaching disks, see [“Managing Devices in ZFS Storage Pools”](#) in *Oracle Solaris ZFS Administration Guide*.

More Information Next Steps

If you install multiple operating systems on your machine, you need to instruct the GRUB boot loader to recognize these operating systems in order to boot. For more information, see [“Modifying Boot Behavior by Editing the GRUB Menu at Boot Time”](#) in *System Administration Guide: Basic Administration*.

Troubleshooting If you encounter any problems during the installation, see [Appendix A, “Troubleshooting \(Tasks\)”](#) in *Oracle Solaris 10 8/11 Installation Guide: Custom JumpStart and Advanced Installations*.

Index

A

- Auto Registration cursor data entry screen, 41, 57, 73, 86
- Auto Registration GUI data entry screen, 40, 56
- Auto Registration screen, 39, 55
- Auto Registration text screen, 39, 55–56, 72, 86

B

- BIOS
 - requirements, 46, 78
 - setting boot priority, 48, 78
- boot priority
 - setting in system BIOS, 48, 78
- booting the system
 - SPARC based systems, 34
 - for ZFS, 65
 - x86 based systems, 48
 - for ZFS, 78

C

- checklist of installation information, 17–28
- commands to start an installation
 - SPARC based systems, 35
 - x86 based systems, 50
- Core System Support Software Group
 - description, 15–17
 - size, 16
- custom installation, description, 38

D

- Developer Oracle Solaris Software Group
 - description, 15–17
 - size, 16
- device drivers, installing, 50
- device settings, modifying, 35, 51, 66
 - for ZFS, 79
- disk space, requirements for software groups, 16

E

- End User Oracle Solaris Software Group
 - description, 15–17
 - size, 16
- Entire Oracle Solaris Software Group
 - description, 15–17
 - size, 16
- Entire Oracle Solaris Software Group Plus OEM Support
 - description, 15–17
 - size, 16

G

- gathering information before installing, 17–28
- graphical user interface (GUI)
 - command to start (SPARC based systems), 35
 - command to start (x86 based systems), 50
 - description, 12
 - memory requirements, 12

GRUB, installing x86 based systems with, 45–61
for ZFS, 77–90

I

information required for installation, 17–28

install time updates (ITUs), installing, 50

installing

device drivers, 50

information required, 17–28

install time updates (ITUs), 50

SPARC based systems, 31–44

for ZFS, 65

x86 based systems, 45–61

for ZFS, 77–90

installing, x86 systems with GRUB, 45–61

for ZFS, 77–90

instructions

installing SPARC based systems, 31–44

installing x86 based systems, 45–61

for ZFS, 77–90

IP addresses, specifying a default route, 25

K

Kerberos, information to configure, 21

keyboard, configuring for SPARC based systems, 35, 66

keyboard, configuring for x86 based systems, 51

for ZFS, 79

L

languages, selecting during installation, 37, 53, 67

for ZFS, 80

log files

upgrade installation, 43, 75, 88

M

media required to install

SPARC based systems, 32

media required to install (*Continued*)

x86 based systems, 45, 77

memory requirements for displaying the Oracle Solaris
installation program, 12

modifying device settings during installation, 35, 51,
66

for ZFS, 79

O

Oracle Solaris installation program, 31–61

Auto Registration cursor data entry screen

SPARC based systems, 41, 57, 73, 86

Auto Registration GUI data entry screen

SPARC based systems, 40, 56

Auto Registration GUI screen

SPARC based systems, 39, 55

Auto Registration text screen

SPARC based systems, 39, 55–56, 72, 86

description, 12–13

graphical user interface (GUI)

command to start (SPARC based systems), 35

command to start (x86 based systems), 50

description, 12

memory requirements, 12

Ready to Install screen

SPARC based systems, 42

x86 based systems, 58

SPARC based systems instructions, 32–44

text installer

command to start in console session (SPARC
based systems), 35

command to start in console session (x86 based
systems), 51

command to start in desktop session (SPARC
based systems), 35

command to start in desktop session (x86 based
systems), 50

description, 12

x86 based systems instructions, 45–61

output files

upgrade log, 43, 75, 88

P

- partition, description, 10
- preparing for installation
 - information you need before installing, 17–28
 - SPARC based systems, 32
 - x86 based systems, 45
 - for ZFS, 77
- prerequisites for installing
 - SPARC based systems, 32
 - x86 based systems, 45
 - for ZFS, 77

R

- Ready to Install screen, 42
- Reduced Network Support Software Group
 - description, 15–17
 - size, 16
- requirements, 10–17
 - BIOS, 46, 78
 - for displaying Oracle Solaris installation program, 12
 - media
 - SPARC based systems, 32
 - x86 based systems, 45, 77
 - memory, 11

S

- serial console, 49
- setting boot priority in system BIOS, 48, 78
- setting up a serial console, 49
- slice, description, 10
- software groups, 16
- Solaris installation program, GRUB
 - instructions, 45–61
- SPARC based systems
 - instructions to install, 31–44
 - preparing to install, 32
- starting an installation
 - SPARC based systems, 35
 - x86 based systems, 50
- stty command, 27

system requirements, 10–17

T

- text installer
 - command to start in console session (SPARC based systems), 35
 - command to start in console session (x86 based systems), 51
 - command to start in desktop session (SPARC based systems), 35
 - command to start in desktop session (x86 based systems), 50
 - description, 12
 - installing ZFS root pools, 63–90
 - memory requirements, 12

U

- upgrade
 - log file, 43, 75, 88
- upgrading
 - postinstallation tasks
 - SPARC based systems, 43
 - x86 based systems, 59
 - SPARC based systems, 31–44
 - SPARC based systems instructions, 32–44
 - x86 based systems, 45–61
 - for ZFS, 77–90
 - x86 based systems instructions, 45–61
 - for ZFS, 77–90

X

- x86 based systems
 - BIOS requirements, 46, 78
 - booting, 48
 - for ZFS, 78
 - installing with GRUB, 45–61
 - for ZFS, 77–90
 - instructions to install, 45–61
 - for ZFS, 77–90

x86 based systems (*Continued*)
 preparing to install, 45
 for ZFS, 77