

Oracle FLEXCUBE Core Banking

Branch Operations User Manual
Release 5.1.0.0.0

Part No. E57304-01

September 2014

ORACLE®

Branch Operations User Manual
September 2014

Oracle Financial Services Software Limited
Oracle Park
Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:

Phone: +91 22 6718 3000

Fax: +91 22 6718 3001

www.oracle.com/financialservices/

Copyright © 2014, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Table of Contents

1. Preface	5
2. Branch Operations	7
3. Operational Control and Cash Management Transactions	9
3.1. Supervisor	13
3.1.1. 6001 - Batch Open	13
3.1.2. 6002 - Branch Batch Close	15
3.1.3. 6005 - Branch Batch Confirm	17
3.1.4. 6009 - Force Close Branch Batch	21
3.1.5. 9888 - Set Initial Cash	23
3.2. Vault Teller	26
3.2.1. 9003 - Open Vault Batch	26
3.2.2. 9009 - Buy Cash From Central Bank	30
3.2.3. 9010 - Sell Cash To Central Bank	34
3.2.4. 9006 - Close Vault Batch	38
3.3. IV003 - Inventory Inter-Branch Transfer	43
3.4. Teller	46
3.4.1. 9001 - Open Teller Batch	46
3.4.2. 9007 - Buy Cash From Vault	51
3.4.3. 9008 - Sell Cash To Vault	55
3.4.4. 6201 - Cash Balancing	58
3.5. 7551 - Book Shortage	62
3.6. 7552 - Book Cash Overage	66
3.7. 9005 - Close Teller Batch	69
3.8. 6203 - TC Balancing*	75
3.9. 6202 - Inventory Balancing	79
3.10. 8007 - Book or Cancel Overage/Shortage	82
3.11. 9030- Buy Cash From Teller	86
3.12. 9013 Buy Inventory From Teller	89
3.13. TIL01- TIL ID Maintenance	92
3.14. TIL02- TIL ID Linkage Maintenance	95
4. Other Transactions	101
4.1. TIL10- TIL Template Maintenance	102
4.2. 4501 - Centralised Authorisation	106
4.3. BA995 - Single Account Transfer	111
4.4. BA999 - Bulk Account Transfer	114
4.5. 5514 - Change Data Entry Batch User	117
4.6. 5515 - List Batch Status	120
4.7. 9800 - Print Spooled Documents	124
4.8. BA123 - Payment Verification Mandate Maintenance*	127
4.9. LN032-Subsidy Payments Instructions	130
4.10. BA888 - User Dashboard	133
4.11. APM04 - Attribute Application Maintenance	136
5. Inquiries	139
5.1. 7012 - Account No Check Digit Inquiry	140
5.2. 7017 - Batch Status Inquiry	142
5.3. BAM95 - Branch Batch Status - Inquiry	144
5.4. 7041 - Branch Totals Position	148
5.5. 7122 - Cross Rate Enquiry	152
5.6. 7008 - Last Ten Transactions	155
5.7. 7050 - Old To New Account Inquiry	158
5.8. 6006 - Search Electronic Journal	161

5.9. 7040 - Teller Totals Position	170
5.10. 7015 - Teller Transactions Summary	174
5.11. 6010 - View Teller Errors	177
5.12. 6007-Transaction - Position Squaring Rate x-ref.....	180
6. Report Generation Transactions.....	185
6.1. BAM16 - Report Control Maintenance	186
6.2. 7775 - Report Request.....	191
6.3. 7780 - Advice/Report Cancel Request.....	194
6.4. 7781 - Report Cancel All Tellers	197
6.5. 7779 - Report Print All Tellers	200
6.6. 7778 - Advice/Report Status Inquiry	204

1. Preface

1.1. Intended Audience

This document is intended for the following audience:

- Customers
- Partners

1.2. Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

1.3. Access to OFSS Support

<https://support.us.oracle.com>

1.4. Structure

This manual is organized into the following categories:

Preface gives information on the intended audience. It also describes the overall structure of the User Manual

Introduction provides brief information on the overall functionality covered in the User Manual

Chapters are dedicated to individual transactions and its details, covered in the User Manual

1.5. Related Information Sources

For more information on Oracle FLEXCUBE Core Banking Release 5.1.0.0.0, refer to the following documents:

- Oracle FLEXCUBE Core Banking Licensing Guide

2. Branch Operations

Branch operations form the key element of the financial service provider's infrastructure, with an objective to augment customer service systems and improve internal efficiencies.

Branch Operations (BROP) in **FLEXCUBE Retail** terminology covers internal activities done at branches where the customer is not involved. From the branch management perspective, the **BROP** module of **FLEXCUBE Retail** facilitates activities, which include controlling the branch vault, opening and closing the branch for the day, and monitoring the transactions done during the day teller-wise and generation of adhoc reports.

FLEXCUBE Retail can work in the offline mode also. When the branch to the local office/ head office central data center link is down, the teller terminals are said to be off-line. In this mode, teller transactions may still be performed and stored at the branch. Later, when the link is up, the stored transactions may be automatically forwarded to the local office.

For all the cash transactions, the system will ask for denomination details only when denomination tracking is enabled.

Key Features

FLEXCUBE Retail Banking Solution offers features in the **BROP** module that allows bank branches to perform internal activities.

- Branch Batch activities that involve opening and closing of the branch
- Cash Management transactions that include managing the teller and vault cash
- Authorization control of teller transactions during the day
- Transactions can be customized to be executed "OFF-LINE"
- Inquiries pertaining to teller transactions and transaction batches
- Report-generation transactions, which include customer advices and statements as well as internal branch reports

Terminologies

The following terminologies are used in the **BROP** module:

Batch

A batch is a bunch of transactions performed at a time as an activity by respective users at different levels in a bank. Certain parameters can be configured to define a batch for users at different levels such as, branch batch, vault batch and teller batch. Each user can perform the batch depending on the rights given to the user, and the kind of transactions she/he is going to perform.

Branch Batch

A branch batch is the process by which a supervisor initiates a branch open. The supervisor is allowed to open the branch for running the business for a particular posting date, and close the branch batch when all the transactions have been successfully processed to a logical end. The vault teller batch followed by the individual teller batch can start the activities, only after the branch batch is opened. The branch batch can be closed only if the individual teller batch followed by Vault teller batch is closed. The branch batch can be closed only once, for a particular posting date.

Vault Batch

A vault batch is a set of transactions performed by the vault teller or chief cashier during a posting date. All transactions such as buying cash from the Central Bank and the cashier of the bank, or selling cash to the Central Bank and the teller, and settling the cash with the Central Bank and the cashier are performed during the posting date before closing the vault batch.

Teller Batch

A teller batch is a set of transactions performed by an individual teller or the cashier. All transactions performed during a posting date should be closed only once.

Split Day Processing

If a branch batch could not be closed for a posting date due to an emergency, the system facilities the branch to open a branch batch for the next posting date to process the transaction. Thus, a branch can process the transactions for multiple days.

Database

Database in **FLEXCUBE Retail**, refers to organized data, stored on a server that can be searched and retrieved by a computer program. The database located at the Central office is known as Host database, and the database located at the branch level is known as Branch database.

3. Operational Control and Cash Management Transactions

To mitigate or limit operational risks, the bank management implements a number of specific measures within the branch. This includes taking care of the sequence of activities performed by a branch for every posting date on **FLEXCUBE Retail**.


The operational controls to initiate branch operations require clearly defined procedures establishing a control environment, which provides authorisation and authentication of transactions.

FLEXCUBE Retail maintains cash balances both currency-wise and teller-wise. Every committed cash transaction taken to its logical end affects the previously mentioned cash balance. Hence, at any given point of time, the physical cash present with a teller has to match with that in the system. In addition, each of the above cash transactions passes GL entries to the cash GL thus affecting the cash GL balances. Thus the consolidated total of all the teller cash balances, together with the vault teller cash balance, has to match with the balance in the cash GL for that branch.

In a cash balancing exercise for each teller, the system displays the system cash balance with that specific teller and requests for a match with the physical cash held by the teller. In case of a mismatch in the above exercise, the teller has to book an Overage or Shortage depending on the mismatch, and proceed with the cash balancing exercise.

The functions could be broadly classified into:


Supervisor Functions



Vault Teller Functions



Teller Functions



Ideally, in a bank, a supervisor opens the branch batch and then the vault teller performs cash activities. The tellers then open their respective batches and buy cash from the vault teller.

At the end of the processing day after all the transactions are completed, the tellers sell cash to the vault teller, if required, and then close their respective batches. After which the vault teller closes the vault batch and then the supervisor closes the branch batch for that day.

3.1. Supervisor

3.1.1. 6001 - Batch Open

Using this option the branch operations can be initiated for a specified date. This option can be executed from any workstation by any supervisor with access rights.

The tellers will not be able to perform any branch operations till the branch batch is opened by the supervisor.

The system allows the branch to be active for a maximum of two consecutive posting dates at a time by specifying the current and the next posting dates. Although a branch batch can be opened for two consecutive days teller batches can be opened only for one posting date at any given time.

The teller batch can be opened for the next posting date, only when it has been closed for the current posting date or it has not been opened for the current posting date. The teller batches cannot be opened for a posting date till the branch batch is opened for that date. When a branch batch is closed for a day by the supervisor the next working day is determined automatically by the system based on the branch calendar present in the branches.

Definition Prerequisites

- BA090 - Bank Calendar Maintenance


Modes Available

Not Applicable

To open a branch batch

1. Type the fast path **6001** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Batch > Batch Open**.
2. The system displays the **Batch Open** screen.

Batch Open



Batch Open*

Posting Date : 15/02/2008

OK Close Clear

Field Description

Field Name	Description
Posting Date	<p>[Mandatory, dd/mm/yyyy]</p> <p>Type the posting date to open a new branch batch.</p> <p>By default the system displays the current date.</p> <p>In case of a split day processing, the system displays the current posting date. Change this date to a new posting date if the user wants to open a new branch for the next posting date.</p> <p>Opening of the branch batch for a particular date indicates to the head office that the branch is open for business operations for the selected date.</p>

3. Click the **Ok** button.

3.1.2. 6002 - Branch Batch Close

Using this option, the branch batch has to be closed, after confirming that all branch transactions have been accounted for in the account books, through the **Confirming Branch Batch** (Fast Path: 6005) option.

The branch batch can be closed to stop the operations for a specified date using the **Branch Batch Close** option. All the teller batches and the vault batches of that branch have to be closed before closing the branch batch for that posting date.

In case of split days, where the branch batch is opened for two consecutive posting dates, the branch batch should be closed in the ascending order, i.e. the branch batch with the previous posting date should be closed first followed by the branch batch with the later posting date. The posting date for closing a branch batch should be the same date on which the respective branch batch was opened.

Definition Prerequisites

- 9005 - Close Teller Batch
- 9006 - Close Vault Batch


Modes Available

Not Applicable

To close a branch batch

1. Type the fast path **6002** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Batch > Branch Batch Close**.
2. The system displays the **Branch Batch Close** screen.

Branch Batch Close



Branch Batch Close*

Posting Date : 15/02/2008

OK Close Clear

Field Description

Field Name	Description
Posting Date	<p>[Mandatory, dd/mm/yyyy]</p> <p>Type the posting date to close an open branch batch.</p> <p>By default, the system displays the date for which the branch batch is open.</p> <p>Closing of the branch batch for a particular date indicates to the head office that the branch is now closed for business operations for the selected date.</p> <p>This date should be the same date for which the branch batch is opened.</p>

3. Click the **Ok** button.

3.1.3. 6005 - Branch Batch Confirm

Transactions done at the branch are posted through the branch database. These posted transactions are picked up by services running on the **FLEXCUBE Retail** Application Server and are finally posted in the host database. This synchronization ensures that ideally, all transactions performed at the branch and posted through the branch database are also present in the host database.

However in some situations, all transactions posted in the branch database do not get posted in the host database. This happens when the link between the branch database and the host database goes down or when the requisite services fail to pick up such branch transactions. There can also be a possibility that the transaction posted through the branch database has hit the host database but the transaction has not been completed due to a drop in the link between host and branch databases. In this case, the number of transactions posted at host will be more than the number of transactions posted in the branch. Such cases give rise to a mismatch between the branch and the host in terms of the count and value of transactions.

Branch batch confirmation is a system check to tally the number and amount of transactions processed at the branch with the number and amount of transactions posted to the host database. The details which are used for comparison include the total number of transactions, total amounts of credits and debits, the number of transfer transactions and the number of reversal of transfer transactions, credit reversals and debit reversals during the day. This supervisor option can be run from any workstation by any supervisor with access rights. This is essential to ensure that all transactions taken place at the branch have been accounted in the bank books.

This is an inquiry option and can be run from any workstation, any time, any number of times and by any supervisor having access rights.

Definition Prerequisites

- 6001 - Batch Open

Modes Available

Not Applicable

To confirm a branch batch

1. Type the fast path **6005** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Batch > Branch Batch Confirm**.
2. The system displays the **Branch Batch Confirm** screen.

Branch Batch Confirm

Branch Batch Confirm*

Posting Date : 15/02/2008

	Branch Totals		Host Totals	
Credits :	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
Credit-Reversals :	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
Debits :	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
Debit-Reversal :	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
Transfer :	<input type="text"/>		<input type="text"/>	
Transfer-Reversal :	<input type="text"/>		<input type="text"/>	

OK Close Clear

Field Description

Field Name	Description
Posting Date	<p>[Mandatory, dd/mm/yyyy]</p> <p>Type the posting date to tally the transactions that have been posted on that date.</p> <p>The system, by default, displays the corresponding branch batch date, which has been opened or re-opened.</p> <p>The Branch Batch Confirmation is a system check to tally the count and value of transactions that have been posted, both in the branch and the host databases. This is essential to ensure that all the transactions that have taken place at the branch have been accounted for in the books of account.</p>

Field Name	Description
Branch Totals	<p>[Display]</p> <p>This column displays the details of the transactions that were carried out by all the bank tellers at the branch level.</p> <p>The details include the number of transactions, the total credits and debits amount, the number of transfer transactions, the number of transfer transaction reversals and the number of credit reversals and debit reversals at the end of the current posting date.</p>
Host Totals	<p>[Display]</p> <p>This column displays the details of the transactions that were carried out at the branch level and were successfully posted to the host database.</p> <p>The details include the number of transactions, the total credits and debits amount, the number of transfer transactions, the number of transfer transaction reversals and the number of credit reversals and debit reversals at the end of the current posting date.</p>

3. Click the **Ok** button.
4. The system displays the details of the branch batch confirmation.

Branch Batch Confirm

Branch Batch Confirm*

Posting Date : 15/02/2008

	Branch Totals		Host Totals	
Credits :	457	9,050,399,816,155.94	464	9,050,499,902,057.70
Credit-Reversals :	2	20.00	2	20.00
Debits :	186	718,018,808.74	175	518,008,135.64
Debit-Reversal :	5	10,300,020.00	4	300,020.00
Transfer :	11		10	
Transfer-Reversal :	0		0	

OK Close Clear

5. If there is any outstanding transaction pending then the system displays a message "Some instrument are outstanding for Inward Clearing run". The branch batch confirmation will not proceed unless the transaction is completed.
6. Click the **Close** button.

3.1.4. 6009 - Force Close Branch Batch

Using this option you can close the branch batch by the branch manager/ supervisor and stop the operations for a specified date, if the normal **Branch Batch Close** (Fast Path: 6002) option fails. Once the branch batch is closed, it cannot be reopened for the same date.

Prior to closing the branch batch, the branch manager or the authorized supervisor has to ensure that all teller batches and vault batches have been closed, and the mismatch displayed in the **Branch Batch Confirm** (Fast Path: 6005) option has been noted down for further investigation.

This is the last option that can be performed for a posting date. However, you can generate reports after running this option.

Definition Prerequisites

- 6001 - Batch Open
- 6005 - Branch Batch Confirm
- 9005 - Close Teller Batch
- 9006 - Close Vault Batch

Modes Available

Not Applicable

To close the branch batch forcefully

1. Type the fast path **6009** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Batch > Force Close Branch Batch**.
2. The system displays the **Force Close Branch Batch** screen.

Force Close Branch Batch

Force Close Branch Batch*

Posting Date :

Please use this option ONLY if Normal Branch Batch Close Option failed

Ensure that you have noted down the Mismatch displayed in the Batch confirm option

OK Close Clear

Field Description

Field Name	Description
Posting Date	<p>[Mandatory, dd/mm/yyyy]</p> <p>Type the posting date to force close the branch batch for that particular date.</p> <p>By default, the system displays the date for which the branch batch is open.</p> <p>Closing of the branch batch for a particular date indicates to the head office that the branch is now closed for business operations for the selected date.</p> <p>This date should be the same date for which the branch batch is opened.</p>

3. Click the **OK** button.

3.1.5. 9888 - Set Initial Cash

Using this option, the supervisor can set the cash position of each teller at the time of initial implementation of the **Oracle FLEXCUBE** branch or at the time of the branch database setup after a branch database crash.

This has to be done for all the currencies for which the teller will carry out the transactions.

Definition Prerequisites

- BAM25 - Currency Definition
- Teller IDs to be created.


Modes Available

Not Applicable

To set initial cash

1. Type the fast path **9888** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Cash > Set Initial Cash**.
2. The system displays the **Set Initial Cash** screen.

Set Initial Cash




The screenshot shows a window titled "Set Initial Cash". Inside the window, there are three input fields at the top left: "Teller Id" with a dropdown menu showing "SDOC5", "Txn Ccy" with a dropdown menu, and "Amount" with a text box. At the bottom right of the window, there are "Ok" and "Cancel" buttons.

Field Description

Field Name	Description
Teller Id	[Mandatory, Drop-Down] Select the user identification of the teller for whom the initial cash has to be set from the drop-down list.
Txn Ccy	[Mandatory, Drop-Down] Select the currency in which the initial cash has to be set from the drop-down list.
Amount	[Mandatory, Numeric, 13, Two] Type the amount which has to be set as initial cash for the teller.
TIL ID	[Display] This field displays the TIL ID to the selected teller ID for which initial cash position is defined.
TIL Description	[Display] This field displays the description of the TIL.

3. Select the currency from the drop-down list.
4. Enter the initial amount.

Set Initial Cash



The image shows a software dialog box titled "Set Initial Cash". It has a yellow title bar with standard window controls (minimize, maximize, close) on the right. The main area is white and contains three input fields: "Teller Id" with a dropdown menu showing "SDOC5", "Txn Ccy" with a dropdown menu showing "INR", and "Amount" with a text box containing "1000". At the bottom right, there are two buttons: "Ok" and "Cancel".

Teller Id : SDOC5

Txn Ccy : INR

Amount : 1000

Ok Cancel

5. Click the **Ok** button.

3.2. Vault Teller

3.2.1. 9003 - Open Vault Batch

Using this option the vault teller can open a vault batch for a specified date. The vault teller is the main cashier of a branch and can be opened from any workstation.

For any given posting date only one vault batch can be opened. To open another vault batch, the first one should be closed. All the tellers buy additional cash or inventory and sell their excess cash or inventory to this teller. The cash/inventory balancing is automatically initiated and the balances are displayed on the screen for confirmation. The system will default the cash balances on opening a vault batch.

Definition Prerequisites

- 6001 - Batch Open
- BAM97 - Currency Codes Cross Reference

Modes Available

Not Applicable

To open a vault batch

1. Type the fast path **9003** and click **Go** or navigate through the menus to **Transaction Processing > Open Vault Batch**.
2. The system displays the **Open Vault Batch** screen.

Open Vault Batch

Field Description

Field Name	Description
Batch Date	<p>[Mandatory, Pick List, dd/mm/yyyy]</p> <p>Select the posting date, to open the vault batch on that date, from the pick list.</p> <p>By default, the system displays the current posting date.</p> <p>Opening of the vault batch for a particular date indicates that all transactions performed by the vault will be stamped with the selected date.</p> <p>This date should be the same date for which the branch batch is opened.</p>
TIL ID	<p>[Display]</p> <p>This field displays the TIL Id linked to the selected vault.</p> <p>TIL can be linked to the vault at the time of vault batch opening.</p>
TIL Description	<p>[Display]</p> <p>This field displays the description of the TIL linked.</p>

- Click the **Ok** button. The system displays the batch opening cash/inventory position for the vault batch.

Cash

Open Vault Batch*

Batch Date : 21/09/2011

TIL ID : 11

TIL Description : RKVAULTTIL

Cash Inventory

Currency	Total Cash	Cash Available
CNY	92638286.00	92638286.00
EUR	0.00	0.00
HKD	0.00	0.00
SGD	0.00	0.00
USD	2671400.00	2671400.00

0 /0

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear


Field Description


Column Name	Description
Currency	[Display] This column displays the currencies in which the bank deals.
Total Cash	[Display] This column displays the total cash for a particular currency, physically present in the bank vault, at the beginning of the current posting date.
Cash Available	[Display] This field displays the cash for a particular currency, which is available in the vault at the beginning of the current posting date, as calculated by the system. The amount displayed in this column depends on the cash transactions that were carried out by the vault till the last posting date.

- Click the **Inventory** tab to view the inventory position at the beginning of the day.

Inventory

Open Vault Batch*

Batch Date : 21/09/2011 

TIL ID : 11  TIL Description : RIKVAULTTIL

Cash **Inventory**

Stock Code	Description	Denomination	Face Value	Available Quantity
0001	REGULAR CHEQUE	1	4614	4614
0002	TRAVELLERS CHEQUES	10	67500	6750
0002	TRAVELLERS CHEQUES	100	773000	7730
0004	Non Personalized Cheque Book	1	3000	3000
0006	DEBIT CARDS	1	4400	4400

0 /0

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

Field Description

Column Name	Description
Stock Code	[Display] This column displays the inventory code.
Description	[Display] This column displays a short description for the inventory.
Denomination	[Display] This column displays the denomination of the inventory.
Face Value	[Display] This column displays the value of the stock. <i>Face Value = Quantity * denomination.</i>
Available Quantity	[Display] This column displays the quantity of stock available with the vault teller at the beginning of the current posting date.

- Click the **OK** button.

3.2.2. 9009 - Buy Cash From Central Bank

The vault teller is the main cashier of a branch. All the tellers will buy additional cash or TC's and will sell their excess cash or TC's to this teller. The vault teller can open a vault batch for a specified date using the **Open Vault Batch** (Fast Path: 9003) option.

Using this option, after opening the vault batch , the vault teller can get cash from the Central Bank and deposit it into the vault. Once the cash is bought from the Central Bank, the system updates the cash position. This transaction is performed by a vault teller.

Definition Prerequisites

- 9003 - Open Vault Batch
- BAM97 - Currency Codes Cross Reference
- Denomination details should be maintained in case denomination-tracking facility is being used.

Modes Available

Not Applicable

To buy cash from central bank

1. Type the fast path **9009** and click **Go** or navigate through the menus to **Transaction Processing > GL Transactions > Cash > Buy Cash From Central Bank**.
2. The system displays the Buy Cash From Central Bank screen.

Buy Cash From Central Bank

Buy Cash From Central Bank*

TIL ID :
Currency :
Ccy Rate :
Amount :
Cheque No :
Narrative :
Buy Cash From Central Bank

TIL Description :

CardChange PinChequeCost RateFCY ChangeDenominationInstrumentInventoryPin ValidationService ChargeSignatureTravellers Cheque

UDFOKCloseClear

Field Description

Field Name	Description
TIL ID	<p>[Optional, Pick List]</p> <p>Select the TIL Id linked to the teller who is selling cash to the vault from the pick list.</p> <p>Supervisor will be able to sell cash from vault for any TIL.</p>
TIL Description	<p>[Display]</p> <p>This field displays the description of the TIL.</p>
Currency	<p>[Mandatory, Drop-Down]</p> <p>Select the currency in which the vault teller wants to buy cash, from the Central Bank, from the drop-down list.</p> <p>For example, the vault teller can buy USD from the Central Bank.</p>

Field Name	Description
Ccy Rate	<p>[Display]</p> <p>This field displays the exchange rate, at which the currency will be purchased from the Central Bank.</p> <p>The currency rate is derived for the option selected in the Currency field.</p> <p>This field displays the effective exchange rate of the selected currency against the local currency of the bank. If the selected currency is the local currency of the bank, the value in this field is defaulted as 1.</p> <p>The rates are defined in the currency table and can be changed by the teller within the variance set at the template level.</p>
Amount	<p>[Mandatory, Numeric, 13, Two]</p> <p>Type the amount that the vault teller wants to purchase from the central bank.</p>
Cheque No	<p>[Optional, Numeric, 12]</p> <p>Type the cheque number against which the cash will be given to the branch by the Central Bank.</p>
Narrative	<p>[Mandatory, Alphanumeric, 40]</p> <p>Type the narration of the transaction.</p> <p>The system displays the default narration "Buy Cash From Central Bank".</p> <p>The vault teller can change the narration, if required.</p>
CIT Vault Code	<p>[Optional, Pick List]</p> <p>Select the CIT vault code from the pick list.</p> <p>The system displays the CIT vault codes maintained in the CIT Vault Codes Maintenance (Fast Path:CIT01) option in the pick list.</p>
CIT Vault Name	<p>[Display]</p> <p>This field displays the CIT vault name corresponding to the option selected in the adjacent field.</p>

3. Select the currency from the drop-down list.
4. Enter the amount.

Buy Cash From Central Bank

Buy Cash From Central Bank*

TIL ID : 999900000000 TIL Description : DeepaliTestTil

Currency : CNY

Ccy Rate : 1.00000

Amount : 1,000.00

Cheque No : 23344

Narrative : Buy Cash From Central Bank

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

5. Click the **Ok** button.
6. The system displays the message "Authorization required. Do you want to continue". Click the **OK** button.
7. The system displays the **Authorization Reason** screen.
8. Enter the relevant information and click the **Grant** button.
9. The system displays the transaction sequence number. The transaction number is system generated that uniquely identifies each transaction performed by a teller and can be used for tracking the transaction. Click the **Ok** button.
10. The system displays the **Document Receipt** screen.
11. If you want to print the receipt, select the record that needs to be printed. The system displays the message "Do You Want To Print". Click the **Ok** button.
OR
Click the **Cancel** button.
12. Click the **Close** button.

Note: For more information on Authorization transactions, refer to the **FLEXCUBE Introduction User Manual**.

3.2.3. 9010 - Sell Cash To Central Bank

Using this option the vault teller can sell cash to the Central Bank from the vault after all the tellers have sold the additional cash to the vault teller. The vault teller cannot close the batch if some excess cash remains at the end of the day.

The amount of cash to be sold by the vault teller cannot exceed the amount of cash held by the vault teller at that point of time. This transaction could be performed even if the vault teller has less cash than the assigned limit.

After the cash is sold to the Central Bank, the system updates the cash position of the vault teller.

If the system maintained cash position is less than the input amount to be sold to the Central Bank, the system displays an error message in which case the transaction should be retried with the correct amount.

Definition Prerequisites

- 9003 - Open Vault Batch
- Denomination details should be maintained in case denomination tracking facility is being used.

Modes Available

Not Applicable

To sell cash to central bank

1. Type the fast path **9010** and click **Go** or navigate through the menus to **Transaction Processing > GL Transactions > Cash > Sell Cash To Central Bank**.
2. The system displays the **Sell Cash To Central Bank** screen.

Sell Cash To Central Bank

Sell Cash To Central Bank*

TIL ID :

TIL Description :

Currency :*

Ccy Rate :

Amount :*

Narrative :*

Sell Cash To Central Bank

Card

Change Pin

Cheque

Cost Rate

FCY Change

Denomination

Instrument

Inventory

Pin Validation

Service Charge

Signature

Travellers Cheque

UDF

OK

Close

Clear

Field Description

Field Name	Description
TIL ID	<p>[Optional, Pick List]</p> <p>Select the TIL Id linked to the teller who is selling cash to the vault from the pick list.</p> <p>Supervisor will be able to sell cash from vault for any TIL.</p>
TIL Description	<p>[Display]</p> <p>This field displays the description of the TIL.</p>
Currency	<p>[Mandatory, Drop-Down]</p> <p>Select the appropriate type of currency that the vault teller wants to sell, to the Central Bank, from the drop-down list.</p> <p>For example, the vault teller can sell USD from Central Bank.</p>

Field Name	Description
Ccy Rate	<p>[Display]</p> <p>This field displays the exchange rate at which the currency will be sold to the Central Bank.</p> <p>The currency rate is derived for the option selected in the Currency field.</p> <p>This field displays the exchange rates of the selected currency against the local currency of the bank. If the selected currency is the local currency of the bank, the value in this field is defaulted as 1.</p> <p>The rates are defined in the currency table and can be changed by the teller within the variance set, at the template level.</p>
Amount	<p>[Mandatory, Numeric, 13, Two]</p> <p>Type the amount that the vault teller wants to sell to the Central Bank.</p>
Narrative	<p>[Mandatory, Alphanumeric, 40]</p> <p>Type the narration of the transaction.</p> <p>The system displays the default narration "Sell Cash From Central Bank".</p> <p>The vault teller can change the narration, if required.</p>

3. Select the currency from the drop-down list.
4. Enter the amount.

Sell Cash To Central Bank

Sell Cash To Central Bank*

TIL ID : 999900000000 TIL Description : DeepalTestTil

Currency : CNY

Ccy Rate : 1.00000

Amount : 1,000.00

Narrative : Sell Cash To Central Bank

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

5. Click the **Ok** button.
6. The system displays the message "Authorisation required. Do you want to continue". Click the **Ok** button.
7. The system displays the **Authorization Reason** screen.
8. Enter the relevant information and click the **Grant** button.
9. The system displays the transaction sequence number. The transaction number is system generated that uniquely identifies each transaction performed by a teller and can be used for tracking the transaction. Click the **Ok** button.
10. The system displays the **Document Receipt** screen.
11. If you want to print the receipt, select the record that needs to be printed. The system displays the message "Do You Want To Print". Click the **Ok** button.
OR
Click the **Cancel** button.
12. Click the **Close** button.

Note: For more information on Authorization transactions, refer to the **Oracle FLEXCUBE Introduction User Manual**.

3.2.4. 9006 - Close Vault Batch

Using this option the vault batch can be closed for a specified date. The vault teller can log in and close the vault batch from any workstation. The system will allow the vault teller to close a vault batch only if all teller batches are closed.

Cash balancing is done automatically and cash balances are displayed on the screen for confirmation. There is also a limit, different from the teller cash limit, on the cash that can be held by the vault teller. If the cash held by the vault teller exceeds the specified limit at the end of the day, the excess cash should be sold to the Central Bank. The vault teller can close the batch only after all the tellers of the branch have sold their excess cash to the vault and have closed their respective teller batches.

If there is a difference in the actual total cash/inventory with the vault teller and the cash/inventory available as shown by the system, the vault teller will have to book overage/shortage for the difference before closing the vault batch, till the differences are closed out.

Definition Prerequisites

- 9003 - Open Vault Batch
- All the teller batches have to be closed.

Modes Available

Not Applicable

To close a vault batch

1. Type the fast path **9006** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Batch > Close Vault Batch**.
2. The system displays the **Close Vault Batch** screen.

Close Vault Batch

Close Vault Batch*

Posting Date : *

20/11/2011

TIL ID

Cash

Inventory

Currency	Total Cash	Cash Available	Overage/Shortage
----------	------------	----------------	------------------

0 /0

Card

Change Pin

Cheque

Cost Rate

FCY Change

Denomination

Instrument

Inventory

Pin Validation

Service Charge

Signature

Travellers Cheque

UDF

OK

Close

Clear

Field Description

Field Name	Description
Posting Date	<p>[Mandatory, Pick List, dd/mm/yyyy]</p> <p>Select the posting date, to close the vault batch, from the pick list.</p> <p>By default, the system displays the current posting date.</p> <p>Closing of the vault teller batch for a particular date indicates that the vault teller has completed the transactions and the balancing of cash for the selected date.</p> <p>This date should be the same date for which the vault batch is opened.</p>
TIL ID	<p>[Display]</p> <p>This field displays the TIL Id linked to the selected vault.</p>
TIL Description	<p>[Display]</p> <p>This field displays the description of the TIL linked.</p>
<p>3. Click the Ok button. The system displays the batch closing cash position for the vault batch.</p>	

Cash

Close Vault Batch*

Posting Date :*

20/11/2011

TIL ID

111

TSUBIT9999

Cash

Inventory

Currency	Total Cash	Cash Available	Overage/Shortage
CNY	0	92638286	-92638286
EUR	0	0	0
HKD	0	0	0
SGD	0	0	0
USD	0	2671400	-2671400

Start Session

Stop Session

1

/1

1

Card

Change Pin

Cheque

Cost Rate

FCY Change

Denomination

Instrument

Inventory

Pin Validation

Service Charge

Signature

Travellers Cheque

UDF

OK

Close

Clear

Field Description

Column Name	Description
Currency	[Display] This column displays the currencies in which the bank deals.
Total Cash	[Mandatory, Numeric, 13, Two] Type the total cash for a particular currency, physically present in the bank vault, at the beginning of the current posting date.
Cash Available	[Display] This column displays the cash for a particular currency, which is available in the vault at the closing of the current posting date, as calculated by the system.

Column Name	Description
Overage/Shortage	<p>[Display]</p> <p>This column displays the difference in the amount between the total cash and the available cash with the vault teller, at the end of the current posting date.</p> <p>Based on this difference the overage or the shortage amount is displayed.</p> <p>An overage indicates that the physical cash with the vault teller is more than the available cash as calculated by the system.</p> <p>A shortage indicates that the available cash calculated by the system, is more than the physical cash present with the vault teller.</p>

4. Enter the total cash.
5. Click the **Inventory** tab to view the inventory position.

Inventory

Close Vault Batch*

Posting Date : 20/11/2011

TIL ID : 111 TSUBIT9999

Cash Inventory

Stock Code	Description	Denomination	Total Quantity	Face Value	Available Quantity	Overage/Shortage	Booked Overage	Booked Shortage
0001	REGULAR CHEQUE	1	0	4615	4615	4615	0	0
0002	TRAVELLERS CHEQUES	100	0	968000	9680	9680	0	0
0002	TRAVELLERS CHEQUES	10	0	67500	6750	6750	0	0
0002	TRAVELLERS CHEQUES	500	0	612500	1225	1225	0	0
0003	PASS BOOKS SAVINGS AC	1	0	3695	3695	3695	0	0
0004	Non Personalized Cheque	1	0	3500	3500	3500	0	0
0006	DEBIT CARDS	1	0	127956	127956	127956	123456	0

Start Session Stop Session

1 / 1

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

Field Description

Column Name	Description
Stock Code	[Display] This column displays the inventory code.
Description	[Display] This column displays a short description for the inventory.
Denomination	[Display] This column displays the denomination of the inventory available with the vault teller at the end of the current posting date.
Total Quantity	[Mandatory, Numeric, 10] Type the quantity of physical stock available with the vault teller. This value should match with the count displayed in the Available Quantity column. If there is a mismatch, the vault teller cannot close the batch.
Face Value	[Display] This column displays the value of the stock. <i>Face Value = Quantity * denomination.</i>
Available Quantity	[Display] This column displays the quantity of stock available with the vault teller as calculated by the system.
Overage/Shortage	[Display] This column displays the quantity of stock that is booked as overage or shortage.
Booked Overage	[Display] This column displays the quantity of stock which is booked as overage on the previous day in the system.
Booked Shortage	[Display] This column displays the quantity of stock which is booked as shortage on the previous day in the system.

6. Enter the total quantity available with vault teller.

7. Click the **OK** button.

Note: The system will not allow the vault batch to be opened in case the physical cash/inventory entered is not the same as the system cash/inventory.

3.3. IV003 - Inventory Inter-Branch Transfer

Using this option you can transfer inventory across branch vaults and from HO to branch vault and vice versa. When stocks are transferred, confirmation of physical receipt of stock is required, till that time, stocks are considered as in transit. This transfer is initiated by vault teller.

Definition Prerequisites

- BAM03 - Branch Master Maintenance
- IVM01 - Stock Codes

Modes Available

Not Applicable

To transfer inventory across branches

1. Type the fast path **IV003** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Inventory > Inventory Inter-Branch Transfer**.
2. The system displays the **Inventory Inter-Branch Transfer** screen.

Inventory Inter-Branch Transfer

Inventory Inter-Branch Transfer*

Transfer Type : ☒ Send ☐ Redeve ☐ Return

StockCode : Denomination :

From Branch : To Branch :

Quantity :

Series Number : Start Number : End Number :

Total Value :

AdjustmentReason :

Card Change Pin Cheque Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

Field Description

Field Name	Description
Transfer Type	<p>[Mandatory, Radio Button]</p> <p>Click the appropriate transfer type option.</p> <p>The options are:</p> <ul style="list-style-type: none"> • Send • Receive • Return
Stock Code	<p>[Mandatory, Pick List]</p> <p>Select the stock code from the pick list.</p>
From Branch	<p>[Conditional, Drop-Down]</p> <p>Select the branch from the drop-down list.</p> <p>This field is enabled if Receive option is selected in the Transfer Type section.</p>
Denomination	<p>[Mandatory, Pick List]</p> <p>Select the inventory denomination from the pick list.</p>
To Branch	<p>[Conditional, Drop-Down]</p> <p>Select the branch from the drop-down list.</p> <p>This field is disabled if Receive option is selected in the Transfer Type section.</p>
Quantity	<p>[Mandatory, Numeric, 10]</p> <p>Type the quantity of the inventory to be transferred.</p>
Series Number	<p>[Mandatory, Numeric, 12]</p> <p>Type the series number of the inventory to be transferred.</p>
Start Number	<p>[Mandatory, Numeric, 10]</p> <p>Type the valid start number of the inventory.</p>
End Number	<p>[Display]</p> <p>This field displays the end number of the inventory.</p>
Total Value	<p>[Mandatory, Numeric, 10]</p> <p>Type the total value of the inventory.</p> <p><i>Total Value = Denomination value * quantity of stock.</i></p>
Adjustment Reason	<p>[Optional, Alphanumeric, 40]</p> <p>Type the adjustment reason.</p>

3. Select the transfer type and stock code.
4. Select the branch code from the drop-down list.

5. Select the denomination from the pick list.
6. Enter the quantity, series number, start number and total value.
7. Enter the appropriate information in the relevant field.

Inventory Inter-Branch Transfer

Inventory Inter-Branch Transfer

Transfer Type : ☐ Send ☒ Receive ☐ Return

StockCode : 0001 Denomination : 1

From Branch : BranchB To Branch : BranchA

Quantity : 10 Series Number : 25

Start Number : 002 End Number : 11

Total Value : 10 AdjustmentReason : reconciliation

Start Session Stop Session

Card Change Pin Cheque Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

8. Click the **Start Session** button.
9. Click the **Ok** button.
10. The system displays the message "Authorization Required. Do You Want to continue". Click the **Ok** button.
11. The system displays the **Authorization Reason** screen.
12. Enter the relevant information and click the **Grant** button.
13. The system displays the message "Transaction completed successfully". Click the **OK** button.

3.4. Teller

3.4.1. 9001 - Open Teller Batch

Using this option the teller batch can be opened on a specified date. A teller can initiate the teller batch with the current cash and inventory position that has been retained from the previous day or start with zero cash or inventory and subsequently buy stock from the vault.

The system will default the cash balances on opening a teller batch.

Definition Prerequisites

- 6001 - Batch Open
- 9019 - Transfer Stocks

Modes Available

Not Applicable

To open a teller batch

1. Type the fast path **9001** and click **Go** or navigate through the menus to **Transaction Processing > Open Teller Batch**.
2. The system displays the **Open Teller Batch** screen.

Open Teller Batch

Open Teller Batch*

Posting Date : 21/09/2011

TIL ID :

TIL Description :

Cash | Inventory

Currency	Total Cash	Cash Available	Overage/Shortage

0 / 0

Card | Change Pin | Cheque | Cost Rate | FCY Change | Denomination | Instrument | Inventory | Pin Validation | Service Charge | Signature | Travellers Cheque

UDF | OK | Close | Clear

Field Description

Field Name	Description
Posting Date	<p>[Mandatory, Pick List, dd/mm/yyyy]</p> <p>Select the posting date, to open the teller batch for that day, from the pick list.</p> <p>By default, the system displays the current posting date.</p> <p>Opening of the teller batch for a particular date indicates to the system that all transactions performed by the teller will be stamped with the selected date.</p> <p>This date should be the same date for which the branch batch is opened.</p>
TIL ID	<p>[Mandatory, Pick list]</p> <p>Select the TIL Id from the drop-down list.</p> <p>The values in the drop-down are TIL Id and name as maintained in TIL ID Maintenance screen. If a teller id is already linked to a TIL ID, the TIL ID will be defaulted in text box, else it will be blank and teller can select the TIL to be linked to his/ her ID. The TIL ID's maintained in the branch to which the teller belongs will only be displayed. The TIL IDs which are in available state can only be linked.</p>
TIL Description	<p>[Display]</p> <p>This field displays the description of the TIL linked.</p>

3. Select the TIL Id and name from the drop-down list.
4. Click the **OK** button.
5. The system displays the batch opening cash position for the teller.

Cash

Open Teller Batch*

Posting Date : 21/09/2011 OPEN DATE

TIL ID : 9999126 XXX TIL Description : RK05

Cash | Inventory

Currency	Total Cash	Cash Available	Overage/Shortage
AUD	0	0	0
EGP	0	0	0
CNY	100	100	0
HKD	0	0	0
JPY	0	0	0
KRW	0	0	0
GBP	0	0	0
USD	600001000	600001000	0
EUR	0	0	0

1 / 1

Card | Change Pin | Cheque | Cost Rate | FCY Change | Denomination | Instrument | Inventory | Pin Validation | Service Charge | Signature | Travellers Cheque

UDF OK Close Clear


Field Description


Column Name	Description
Currency	[Display] This column displays the currencies in which the bank deals.
Total Cash	[Display] This column displays the total cash for a particular currency, physically present with the teller, at the beginning of the current posting date.
Cash Available	[Display] This column displays the cash for a particular currency, which is available with the teller at the beginning of the current posting date, as calculated by the system. The amount displayed in this column depends on the transactions carried out by the teller till the last posting date.

- Click the **Inventory** tab to view the batch opening inventory position for the teller.

Inventory

Open Teller Batch*

Posting Date : 21/09/2011 

TIL ID : 999900000000 

TIL Description : TDEEPALI

Cash **Inventory**

Stock Code	Description	Denomination	Face Value	Available Quantity
0001	REGULAR CHEQUE	1	50	50

1 / 1

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument **Inventory** Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

Field Description

Column Name	Description
Stock Code	[Display] This field displays the inventory code.
Description	[Display] This column displays a short description for the inventory.
Denomination	[Display] This column displays the denomination of the inventory available with the teller at the beginning of the current posting date.
Face Value	[Display] This column displays the value of the stock. <i>Face Value = Quantity * denomination.</i>
Available Quantity	[Display] This column displays the quantity of stock available with the teller at the beginning of the current posting date.

Column Name	Description
	[Mandatory, Drop Down]
TIL ID and Name	<p>Select the TIL Id and name from the drop-down list.</p> <p>The values in the drop-down are TIL Id and name as maintained in TIL ID Maintenance screen. If a teller id is already linked to a TIL ID, the TIL ID will be defaulted in text box, else it will be blank and teller can select the TIL to be linked to his/ her ID. The TIL ID's maintained in the branch to which the teller belongs will only be displayed. The TIL IDs which are in available state can only be linked.</p>

6. Click the **OK** button.

3.4.2. 9007 - Buy Cash From Vault

Using this option you can get cash from the vault. After completing this transaction, the system updates the cash position of the vault teller and the teller. If the vault teller's cash position is less than the total cash requested by the teller, the system displays an error message and the teller should perform this transaction after the vault has been replenished.

The teller can buy any amount up to the amount available with vault. If the amount exceeds the maximum limit that the teller is allowed to retain with him/her, the system will prompt the teller to sell the excess cash to the vault using **Sell Cash to Vault** (Fast Path: 9008) option.

Definition Prerequisites

- 9003 - Open Vault Batch
- Denomination details should be maintained in case denomination tracking facility is being used.

Modes Available

Not Applicable

To buy cash from vault

1. Type the fast path **9007** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Cash > Buy Cash From Vault**.
2. The system displays the **Buy Cash From Vault** screen.

Buy Cash From Vault

Field Description

Field Name	Description
TIL ID	<p>[Optional, Pick List]</p> <p>Select the TIL Id linked to the teller who is selling cash to the vault from the pick list.</p> <p>Supervisor will be able to sell cash from vault for any TIL.</p>
TIL Description	<p>[Display]</p> <p>This field displays the description of the TIL.</p>
Currency	<p>[Mandatory, Drop-Down]</p> <p>Select the currency in which the teller wants to buy cash from the vault from the drop-down list.</p> <p>The drop-down list displays only those currencies in which the teller can deal.</p>

Field Name	Description
Total Required Cash	<p>[Mandatory, Numeric, 13, Two]</p> <p>Type the amount that the teller needs to buy from the vault teller.</p> <p>The teller position will get updated as soon as the transaction is completed. If the amount exceeds the maximum limit that the teller is allowed to retain with him/her, the system prompts the teller to sell the excess cash to the vault using Sell Cash to Vault (Fast Path: 9008) option. This can be done either immediately or before the teller batch is closed for the posting date.</p>
Narrative	<p>[Optional, Alphanumeric, 40]</p> <p>Type the narration for the transaction.</p> <p>The system displays the default narration "Buy Cash From Vault".</p> <p>The teller can change the narration, if required.</p>

3. Select the currency from the drop-down list.
4. Enter the total required cash.

Buy Cash From Vault

The screenshot shows a software window titled "Buy Cash From Vault*". Inside the window, there are several input fields: "TIL ID" with the value "999900000000", "Currency" set to "CNY", "Total Required Cash" set to "1,000.00", and "Narrative" set to "Buy Cash From Vault". At the bottom of the window, there is a horizontal bar with buttons for "Card", "Change Pin", "Cheque", "Cost Rate", "FCY Change", "Denomination", "Instrument", "Inventory", "Pin Validation", "Service Charge", "Signature", and "Travellers Cheque". Below this bar, there are four buttons: "UDF", "OK", "Close", and "Clear".

5. Click the **Ok** button.

6. The system displays the transaction sequence number. The transaction number is system generated that uniquely identifies each transaction performed by a teller and can be used for tracking the transaction. Click the **OK** button.
7. The system displays the **Document Receipt** screen.
8. If you want to print the receipt, select the record that needs to be printed. The system displays the message "Do You Want To Print". Click the **Ok** button.
OR
Click the **Cancel** button.
9. Click the **Close** button.

3.4.3. 9008 - Sell Cash To Vault

Using this option you can sell cash at any point of time during the day, if the cash held exceeds the limit set at the template level for any currency. The system will prompt you with regard the cash limit has exceeded and request the teller to sell the additional cash to the vault. You can perform this activity any time during the day or before closing the batch for the posting date. This transaction can be performed even if you have less cash than the assigned limit. The cash position is updated after this transaction is completed.

Definition Prerequisites

- 9001 - Open Teller Batch
- 9003 - Open Vault Batch

Modes Available

Not Applicable

To sell cash from vault

1. Type the fast path **9008** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Cash > Sell Cash To Vault**.
2. The system displays the **Sell Cash To Vault** screen.

Sell Cash To Vault

Sell Cash To Vault*

TIL ID : xxx TIL Description :

Currency : *

Total Cash to be Sold : *

Narrative:

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

Field Description

Field Name	Description
TIL ID	<p>[Optional, Pick List]</p> <p>Select the TIL Id linked to the teller who is selling cash to the vault from the pick list.</p> <p>Supervisor will be able to sell cash from vault for any TIL.</p>
TIL Description	<p>[Display]</p> <p>This field displays the description of the TIL.</p>
Currency	<p>[Mandatory, Drop-Down]</p> <p>Select the currency in which the teller wants to sell cash to the vault from the drop-down list.</p> <p>The drop-down list displays only those currencies in which the teller can deal.</p>
Total Cash to be Sold	<p>[Mandatory, Numeric, 13, Two]</p> <p>Type the amount that the teller needs to sell to the vault.</p> <p>The teller position gets updated as soon as the transaction is complete. If the amount exceeds the maximum limit that the teller is allowed to retain with him/her, the system prompts the teller to sell the excess cash to the vault. This can be done immediately or before the teller batch is closed for the posting date.</p>
Narrative	<p>[Mandatory, Alphanumeric, 40]</p> <p>Type the narration for the transaction.</p> <p>The system displays the default narration "Sell Cash To Vault".</p> <p>The teller can change the narration, if required.</p>

3. Select the currency from the drop-down list.
4. Type the total cash to be sold.

Sell Cash To Vault

Sell Cash To Vault*

TIL ID : 999900000000
 Currency : CNY
 Total Cash to be Sold : 1,500.00
 Narrative: Sell Cash To Vault

TIL Description : DeepallTestTil

Card | Change Pin | Cheque | Cost Rate | FCY Change | Denomination | Instrument | Inventory | Pin Validation | Service Charge | Signature | Travellers Cheque

UDF | OK | Close | Clear

5. Click the **Ok** button.
6. The system displays the transaction sequence number. The transaction number is system generated that uniquely identifies each transaction performed by a teller and can be used for tracking the transaction. Click the **OK** button.
7. The system displays the **Document Receipt** screen.
8. If you want to print the receipt, select the record that needs to be printed. The system displays the message "Do You Want To Print". Click the **Ok** button.
 OR
 Click the **Cancel** button.
9. Click the **Close** button.

3.4.4. 6201 - Cash Balancing

Using this option you can check if the physical cash held by a teller / vault teller matches with the system cash for that teller as per **Oracle FLEXCUBE**. This can be verified anytime during the day or before closing the teller batch.

This option displays approved currencies in which the teller / vault teller can perform transactions. The total amount for a particular currency available in the cash drawer / vault should be entered to check the overage/shortage of cash amount maintained in the system.

In case of an overage/shortage for a particular currency, the teller should perform the transaction in the **Book Cash Overage** (Fast Path: 7552) option or **Book Shortage** (Fast Path: 7551) option and then perform the cash balancing transaction again.

Definition Prerequisites

- 9003 - Open Vault Batch
- 9001 - Open Teller Batch

Modes Available

Not Applicable

To view cash balance

1. Type the fast path **6201** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Batch > Cash Balancing**.
2. The system displays the **Cash Balancing** screen.

Cash Balancing

Field Description

Column Name	Description
Teller Id	<p>[Conditional, Pick List, Display]</p> <p>Select the teller ID against who's TIL supervisor needs to perform cash balancing from the pick list.</p> <p>In case if the teller accesses this screen, Teller ID field will be disabled and by default the logged in teller ID will be displayed.</p>
TIL Id	<p>[Display]</p> <p>This column displays the TIL ID linked to the selected teller ID.</p>
TIL Description	<p>[Display]</p> <p>This column displays the description of the TIL linked.</p>
Currency	<p>[Display]</p> <p>This column displays the currency codes in which the teller / vault teller can perform transactions.</p>

Column Name	Description
Total Counted Cash	<p>[Mandatory, Numeric, 13, Two]</p> <p>Type the total cash for the particular currency, which is physically present with the teller on the current posting date.</p>
Cash Available	<p>[Display]</p> <p>This column displays the cash available with the teller, as calculated by the system, on the current posting date.</p>
Overage/Shortage	<p>[Display]</p> <p>This column displays the difference in the amount between the total counted cash and the available cash with the teller.</p> <p>Based on this difference, either the overage or shortage amount is displayed.</p> <ul style="list-style-type: none"> • Overage: If the physical cash held by the teller in a particular currency exceeds the amount of cash in that currency for the teller as shown by the system, the excess amount of that currency is known as overage. The overage amount is displayed with a '+' sign. • Shortage: If the physical cash held by the teller in a particular currency is less than the amount of cash in that currency for the teller as shown by the system, the shortage amount of that currency is known as shortage. The shortage amount is displayed with a '-' sign.

3. Enter the total counted cash for the respective currencies.

Cash Balancing

Cash Balancing*

Teller ID: TSUBIT9999
 TIL ID: 111
 TIL Description: TSUBIT9999

Currency	Total Counted Cash	Cash Available	Overage/Shortage
AUD	0.00	0.00	0.00
EGP	0.00	0.00	0.00
CNY	0.00	3,876,411.25	-3,876,411.25
HKD	0.00	0.00	0.00
JPY	0.00	0.00	0.00
KRW	0.00	0.00	0.00
GBP	0.00	0.00	0.00
USD	0.00	0.00	0.00
EUR	0.00	0.00	0.00

Card | Change Pin | Cheque | Cost Rate | FCY Change | Denomination | Instrument | Inventory | Pin Validation | Service Charge | Signature | Travellers Cheque

UDF OK Close Clear

- Click the **OK** button.
- If there is an overage/shortage the system will display the cash not balanced message.
- Click the **Close** button.

3.5. 7551 - Book Shortage

Using this option the teller / vault teller can book the shortage, if the actual/physical cash present with the teller / vault teller is less than the system cash.

While booking a shortage, the system lowers the cash balance and brings it in sync with the physical cash balance with the teller by passing the difference to a cash shortage GL. Once the system cash and the physical cash are synchronized, the teller has to perform the cash balancing.

Definition Prerequisites

- 9001 - Open Teller Batch
- 9003 - Open Vault Batch
- BAM56 - Currency Code Maintenance

Modes Available

Not Applicable

To book a shortage

1. Type the fast path **7551** and click **Go** or navigate through the menus to **Transaction Processing > GL Transactions > Cash > Book Shortage**.
2. The system displays the **Book Shortage** screen.

Book Shortage

Book Shortage*

Teller ID: TSUBIT9999

TIL ID: 111

TIL Description: TSUBIT9999

Currency: *

Amount: *

Narrative: Book Shortage

Reference Number: *

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

Field Description

Field Name	Description
Teller Id	<p>[Conditional, Pick List, Display]</p> <p>Select the teller ID against who's TIL supervisor needs to book cash shortage from the pick list.</p> <p>In case if the teller accesses this screen, Teller ID field will be disabled and by default the logged in teller ID will be displayed.</p>
TIL Id	<p>[Display]</p> <p>This column displays the TIL ID linked to the selected teller ID.</p>
TIL Description	<p>[Display]</p> <p>This column displays the description of the TIL linked.</p>
Currency	<p>[Mandatory, Drop-Down]</p> <p>Select the currency for which the teller wants to book the shortage from the drop-down list.</p> <p>The drop-down list displays only those currencies in which the teller can deal.</p>

Field Name	Description
Amount	[Mandatory, Numeric, 13, Two] Type the shortage amount. The system will reduce the calculated cash balance by this amount, to synchronize the same with the cash balance, which is physically held by the teller.
Narrative	[Mandatory, Alphanumeric, 40] Type the narration of the transaction. The system displays the default narration "Book Shortage". The vault teller can change the narration, if required.
Reference Number	[Mandatory, Alphanumeric, 16] Type the reference number for the transaction.

3. Select the currency from the drop-down list.
4. Enter the amount and the reference number for the shortage.

Book Shortage

Book Shortage*

Teller ID: TSUBIT9999

TIL ID: 111 TIL Description: TSUBIT9999

Currency: CNY

Amount: 1,000.00

Narrative: Book Shortage

Reference Number: 7888

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

5. Click the **Ok** button.
6. The system displays the message "Authorization Required. Do you want to continue". Click the **OK** button.

7. The system displays the **Authorization Reason** screen.
8. Enter the required information and click the **Grant** button.
9. The system displays the transaction sequence number. The transaction number is system generated that uniquely identifies each transaction performed by a teller and can be used for tracking the transaction. Click the **OK** button.
10. The system displays the **Document Receipt** screen.
11. If you want to print the receipt, select the record that needs to be printed. The system displays the message "Do You Want To Print". Click the **Ok** button.
OR
Click the **Cancel** button.
12. Click the **Close** button.

Note: For more information on Authorization transactions, refer to the *Oracle FLEXCUBE Introduction User Manual*.

3.6. 7552 - Book Cash Overage

Using this option the teller / vault teller has to book the physical cash held in a particular currency, which exceeds the cash in that currency as shown by the system. The teller can close the batch for a posting date only if the cash balances tally.

While booking a cash overage, the system increases the cash balance and brings it in sync with the physical balance with the teller, by passing the difference to a cash overage liability GL.

Definition Prerequisites

- BAM56 - Currency Codes Maintenance
- The vault batch and the teller batch should be opened for the posting date.

Modes Available

Not Applicable

To book an overage

1. Type the fast path **7552** and click **Go** or navigate through the menus to **Transaction Processing > GL Transactions > Cash > Book Cash Overage**.
2. The system displays the **Book Cash Overage** screen.

Book Cash Overage

Book Cash Overage*

Teller ID: TSUBIT9999

TIL ID: 111

TIL Description: TSUBIT9999

Currency: *

Amount: *

Narrative: * Book Cash Overage

Reference Number: *

Card | Change Pin | Cheque | Cost Rate | FCY Change | Denomination | Instrument | Inventory | Pin Validation | Service Charge | Signature | Travellers Cheque

UDF | OK | Close | Clear

Field Description

Field Name	Description
Teller Id	<p>[Conditional, Pick List, Display]</p> <p>Select the teller ID against who's TIL supervisor needs to book cash overage from the pick list.</p> <p>In case if the teller accesses this screen, Teller ID field will be disabled and by default the logged in teller ID will be displayed.</p>
TIL Id	<p>[Display]</p> <p>This column displays the TIL ID linked to the selected teller ID.</p>
TIL Description	<p>[Display]</p> <p>This column displays the description of the TIL linked.</p>
Currency	<p>[Mandatory, Drop-Down]</p> <p>Select the currency for which the teller wants to book the overage from the drop-down list.</p>
Amount	<p>[Mandatory, Numeric, 13, Two]</p> <p>Type the overage amount.</p> <p>The system will increase the system-calculated cash balance by this amount, to synchronize the same with the cash balance, which is physically held by the teller.</p>
Narrative	<p>[Mandatory, Alphanumeric, 40]</p> <p>Type the narration.</p> <p>The system displays the default narration "Book Cash Overage".</p> <p>The vault teller can change the narration, if required.</p>
Reference Number	<p>[Mandatory, Alphanumeric, 16]</p> <p>Type the reference number for the transaction.</p>

3. Select the currency from the drop-down list.
4. Enter the amount and the reference number for the transaction.

Book Cash Overage

Book Cash Overage*

Teller ID: TSUBIT9999
 TIL ID: 111
 TIL Description: TSUBIT9999
 Currency : CNY
 Amount : 1,000.00
 Narrative : Book Cash Overage
 Reference Number : 87745

Card | Change Pin | Cheque | Cost Rate | FCY Change | Denomination | Instrument | Inventory | Pin Validation | Service Charge | Signature | Travellers Cheque

UDF OK Close Clear

5. Click the **Ok** button.
6. The system displays the message "Authorization Required. Do You Want to Continue". Click the **Ok** button.
7. The system displays the **Authorization Reason** screen.
8. Enter the relevant information and click the **Grant** button.
9. The system displays the transaction sequence number. The transaction number is system generated that uniquely identifies each transaction performed by a teller and can be used for tracking the transaction. Click the **Ok** button.
10. The system displays the **Document Receipt** screen.
11. If you want to print the receipt, select the record that needs to be printed. The system displays the message "Do You Want To Print". Click the **Ok** button.
OR
Click the **Cancel** button.
12. Click the **Close** button.

Note: For more information on authorization transactions, refer to the *Oracle FLEXCUBE Introduction User Manual*.

3.7. 9005 - Close Teller Batch

Using this option you can close the teller batch for the given posting date.

The system allows the teller batch to be closed for the day only when all the transactions are successfully processed. In case any transaction is pending, like an unauthorized or an incomplete batch data entry, the system prompts you to either complete or reverse the transactions so that the teller can close the batch for the day. In addition to this, there is a specified limit on the cash that a teller can retain at the end of the day. The bank maintains the specified limit for each currency. Whenever a transaction is performed or while closing the teller batch, the system checks the cash balances for each currency with the respective limits and prompts the teller in case of violation. If the limit is exceeded, the teller sells the excess cash to the main vault, to bring his cash holding within the retention limit. After selling the excess cash the teller has to ensure that the physical cash held, is same as that shown by the system.

For a teller, if there is a difference in the physical cash/inventory and that calculated by the system, the overage or shortage has to be booked accordingly and only then each teller can close the teller batch for that day.

Before closing the teller batch, the teller should ensure completion of all the incomplete batches for consolidated cheques, outward clearing batches, inward clearing batches, etc. This is applicable if the teller has done the header transaction of the consolidated cheque deposit but has not performed the detailed data entry of consolidated cheques. Once it is closed, the teller batch cannot be re-opened for the same posting date.

Definition Prerequisites

- 9001 - Open Teller Batch
- 9003 - Open Vault Batch

Modes Available

Not Applicable

To close a teller batch

1. Type the fast path **9005** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Batch > Close Teller Batch**.
2. The system displays the **Close Teller Batch** screen.

Close Teller Batch

Close Teller Batch*

Please ensure that the following has been done...

Cheque Data Entry Completed Successfully

Posting Date : 20/11/2011

TIL ID : 111

Delink ☐

TIL Description TSUBIT9999

Cash Inventory

Currency	Total Cash	Cash Available	Overage/Shortage

0 /0

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

Field Description

Field Name	Description
Posting Date	<p>[Mandatory, Pick List, dd/mm/yyyy]</p> <p>Select the posting date, for which the teller batch is to be closed, from the pick list.</p> <p>By default, the system displays the current posting date.</p> <p>Closing of the teller batch for a particular date indicates that the teller has completed the transactions and the balancing of cash for the selected date.</p> <p>This date should be the same date for which the teller batch is opened.</p>
TIL ID	<p>[Display]</p> <p>This field displays the TIL Id if it is linked to the logged in Teller Id.</p> <p>This field displays as blank, if no TIL ID is linked.</p>
TIL Description	<p>[Display]</p> <p>This field displays the description of the TIL linked.</p>

Field Name	Description
Delink	[Conditional, Check Box] Select the Delink Checkbox to Delink the TIL ID and Name from the Teller .

- Click the **Ok** button. The system displays the cash details.
- Enter the total cash.

Cash

Close Teller Batch*

Please ensure that the following has been done...

Cheque Data Entry Completed Successfully

Posting Date : 20/11/2011 TIL ID : 111

Delink ☐ TIL Description TSUBIT9999

Cash | Inventory

Currency	Total Cash	Cash Available	Overage/Shortage
RMB	0	1219800	-1219800
GBP	0	0	0
HKD	0	0	0
USD	0	0	0
CHF	0	0	0
SGD	0	0	0
EUR	0	0	0
JPY	0	0	0
CAD	0	0	0
AUD	0	0	0
KRW	0	0	0
MOP	0	0	0
INR	0	0	0
SAD	0	0	0
YEN	0	0	0
MSC	0	0	0
THB	0	0	0
FRC	0	0	0
SUN	0	0	0
IDR	0	0	0

1 / 2 1 2

Card | Change Pin | Cheque | Cost Rate | FCY Change | Denomination | Instrument | Inventory | Pin Validation | Service Charge | Signature | Travellers Cheque

UDF OK Close Clear

Field Description

Column Name	Description
Currency	[Display] This column displays the currencies in which the bank deals.

Column Name	Description
Total Cash	<p>[Mandatory, Numeric, 13, Two]</p> <p>Type the total cash for a particular currency, physically present with the teller, at the end of the current posting date.</p> <p>This amount should match with the cash displayed in the Cash Available column. If there is a mismatch in the amounts, the teller cannot close the batch.</p>
Cash Available	<p>[Display]</p> <p>This column displays the amount for a particular currency, which is available with the teller at the end of the current posting date.</p> <p>This amount is calculated by the system and depends on the transactions carried out by the teller on the current posting date.</p>
Overage/Shortage	<p>[Display]</p> <p>This column displays the difference in the amount between the total cash and the available cash with the teller, at the end of the current posting date.</p> <p>Based on this difference the overage or the shortage amount is displayed.</p> <p>An overage indicates that the physical cash with the teller is more than the available cash as calculated by the system.</p> <p>A shortage indicates that the available cash calculated by the system, is more than the physical cash present with the teller.</p>


5. Click the **Inventory** tab to view the closing inventory position for the teller.
6. Enter the total quantity.

Inventory

Close Teller Batch*

Please ensure that the following has been done...

Cheque Data Entry Completed Successfully

Posting Date : 20/11/2011  TIL ID : 111

Delink ☐ TIL Description TSUBIT9999

Cash **Inventory**

Stock Code	Description	Denomination	Total Quantity	Face Value	Available Quantity	Overage/Shortage	Booked Overage	Booked Shortage
731	Cash Cheque	50	0	550	11	11	0	0

1 / 1

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

Field Description

Column Name	Description
Stock Code	[Display] This column displays the inventory code.
Description	[Display] This column displays a short description for the inventory.
Denomination	[Display] This column displays the denomination of the inventory available with the teller at the end of the current posting date.
Total Quantity	[Mandatory, Numeric, 10] Type the quantity of stock available with the teller. This value should match with the count displayed in the Available Quantity column. If there is a mismatch, the teller cannot close the batch.

Column Name	Description
Face Value	[Display] This column displays the value of the stock. <i>Face Value = Quantity * denomination.</i>
Available Quantity	[Display] This column displays the quantity of stock available in the system.
Overage/Shortage	[Display] This column displays the quantity of stock that is booked as overage or shortage.
Booked Overage	[Display] This column displays the quantity of stock which is booked as overage on the previous day in the system.
Booked Shortage	[Display] This column displays the quantity of stock which is booked as shortage on the previous day in the system.

7. Click the **Ok** button.
8. Click the **Close** button.

Note: If there is an overage/shortage, the system will display the cash/stock not balanced message.

3.8. 6203 - TC Balancing*

Bank may buy and sell Traveler's cheques from the existing customers as well as walk-in customers. Balancing the TC is a prerequisite for the teller before closing the teller batch for the day.

Using this option, tellers authorized to deal with TC, balance their physical TC in custody with the system count at the beginning of the branch operations. During the day the count is altered vide TC purchases and sales. Balancing the TC is a prerequisite for the teller before closing the teller batch for the day. In case of any overage/shortage of TC, the same is displayed in the screen for the user for reconciliation and balancing.

Definition Prerequisites

- Issuer Maintenance (Fast Path: BAM09)
- BAM56 - Currency Codes Maintenance
- Bank Codes Maintenance (Fast Path: BAM20)

Modes Available

Not Applicable

To inquire on TC balancing

1. Type the fast path **6203** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Batch > TC Balancing**.
2. The system displays the **TC Balancing** screen.

TC Balancing

TC Balancing

Issuer Code : Currency :

Denominations	User Count	Amount	System Count	Amount
Total :				
Overage / Shortage :				

Ok Cancel

Field Description

Field Name	Description
Issuer Code	[Mandatory, Drop Down] Select the issuer bank from the drop down. The same is maintained by the Issuer Maintenance (Fast Path- BAM09) option.
Currency	[Mandatory, Drop Down] Select the currency of the TC in custody of the teller
Denominations	[Display] The denomination of the TC is displayed in this field. TCs of various denominations will be available with the teller.
User Count	[Mandatory, Numeric, 20] Enter the number of TCs of the selected currency and denomination available with the teller.

Field Name	Description
Amount	[Display] The total value of the TCs of the displayed denomination is displayed in this field.
System Count	[Display] This field displays the system count of the TC of the denomination specified.
Amount	[Display] This field displays the amount of the TC as per the system count.
Total	[Display] This field displays the user and system totals across denomination and amount.
Overage / Shortage	[Display] This field displays overage/shortage in TC denomination/amount if any.

3. Select the issuer code and currency from the drop down list.
4. Enter user count denomination-wise.

TC Balancing

TC Balancing				
Issuer Code : <input type="text" value="ALLIED IRISH BANK"/>		Currency : <input type="text" value="USD"/>		
Denominations	User Count	Amount	System Count	Amount
One Hundred	<input type="text" value="10"/>	<input type="text" value="1,000.00"/>	<input type="text" value="20"/>	<input type="text" value="2,000.00"/>
	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>
Total :	<input type="text" value="10"/>	<input type="text" value="1,000.00"/>		<input type="text" value="2,000.00"/>
Overage / Shortage :	<input type="text" value="-10"/>	<input type="text" value="-1,000.00"/>		

5. Click the **Ok** button.
6. If there is any overage, the system displays the message "TC Not Balanced".
7. Click the **Cancel** button.

3.9. 6202 - Inventory Balancing

Using this option you can perform inventory balancing during the day. The total physical inventory quantity belonging to a particular stock is updated after performing the inventory transactions for the day. Once the total quantity is entered, the system compares the total physical quantity with the available system quantity and calculates an Overage/ Shortage (if any). The system also displays any previously booked overage/shortage.

Before closing the teller batch, you must book/cancel inventory overage/shortage and tally the inventory balance.

Definition Prerequisites

Not Applicable

Modes Available

Not Applicable

To view the inventory balancing details:

1. Type the fast path **6202** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Batch > Inventory Balancing**.
2. The system displays the **Inventory Balancing** screen.

Inventory Balancing

Inventory Balancing*

Teller ID: TSUBIT9999

TIL ID: 111

TIL Description: TSUBIT9999

Stock Code	Description	Denomination	Total Quantity	Face Value	Available Quantity	Overage/Shortage	Booked Overage	Booked Shortage

0 /0

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

Field Description

Column Name	Description
Teller Id	[Conditional, Pick List, Display] Select the teller ID against who's TIL supervisor needs to perform inventory balancing from the pick list. In case if the teller accesses this screen, Teller ID field will be disabled and by default the logged in teller ID will be displayed.
TIL Id	[Display] This column displays the TIL ID linked to the selected teller ID.
TIL Description	[Display] This column displays the description of the TIL linked.
Stock Code	[Display] This column displays the inventory code.
Description	[Display] This column displays a short description for the inventory.
Denomination	[Display] This column displays the denomination of the inventory available with the teller.
Total Quantity	[Mandatory, Numeric, 10] Type the quantity of physical stock available with the teller.
Face Value	[Display] This column displays the value of the stock. <i>Face Value = Quantity * denomination.</i>
Available Quantity	[Display] This column displays the quantity of stock available in the system.
Overage/Shortage	[Display] This column displays the quantity of stock that is booked as overage or shortage.
Booked Overage	[Display] This column displays the quantity of stock which is booked as overage on the previous day in the system.
Booked Shortage	[Display] This column displays the quantity of stock which is booked as shortage on the previous day in the system.

- Enter the total quantity of physical inventory available with the teller.

Inventory Balancing

Inventory Balancing*

Teller ID: TSUBIT9999

TIL ID: 111 TIL Description: TSUBIT9999

Stock Code	Description	Denomination	Total Quantity	Face Value	Available Quantity	Overage/Shortage	Booked Overage	Booked Shortage
0001	REGULAR CHEQUE	1	49	50	49	0	0	1
0003	PASS BOOKS SAVINGS AC	1	692	691	692	0	1	0

1 / 1

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

- Click the **Close** button.

3.10. 8007 - Book or Cancel Overage/Shortage

Oracle FLEXCUBE monitors the inventories held by tellers to keep track of available stocks. While closing a teller batch, if the teller realizes that physical quantity in hand is not matching with the system count and teller is not able to find the details of inventory causing shortage or overage, the teller can book overage or shortage of the inventory using this option.

When shortage is booked, the quantity of the inventory for which shortage is booked is reduced from tellers inventory count and the status of such inventory is updated as 'Shortage' and it is not available for issuance. When an overage is booked, the quantity booked as overage gets added to the Tellers inventory count and the status of such inventory is updated as 'Overage' and it will not be available for issue.

When overage or shortage is booked, reconciliation is done manually on the subsequent day and the reason for shortage or overage is identified. The shortage or overage booked is cancelled by using this option. By reverting the booking of shortage/overage, the status and count of the teller inventory is reverted back to original. The status of the inventory for which the shortage/overage was booked has to be updated in the **Stock Adjustment** (Fast Path: IV002) option.

Definition Prerequisites

Not Applicable

Modes Available

Not Applicable

To book or cancel overage/shortage

1. Type the fast path **8007** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transaction > Inventory > Book or Cancel Overage/Shortage**.
2. The system displays the **Book or Cancel Overage/Shortage** screen.

Book or Cancel Overage/Shortage

Book or Cancel Overage/Shortage*

Teller Id : TSUBIT9999

TIL ID : 111 TIL Description : TSUBIT9999

Option : *

Stock Code : *

Denomination : *

Quantity : *

Face Value : *

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

Field Description

Field Name	Description
Teller Id	<p>[Conditional, Pick List, Display]</p> <p>Select the teller ID against who's TIL supervisor needs to book inventory overage/ shortage from the pick list.</p> <p>In case if the teller accesses this screen, Teller ID field will be disabled and by default the logged in teller ID will be displayed.</p>
TIL Id	<p>[Display]</p> <p>This column displays the TIL ID linked to the selected teller ID.</p>
TIL Description	<p>[Display]</p> <p>This column displays the description of the TIL linked..</p>

Field Name	Description
Option	<p>[Mandatory, Drop-Down]</p> <p>Select the inventory adjustment option from the drop-down list.</p> <p>The options are:</p> <ul style="list-style-type: none"> • Book Overage • Book Shortage • Cancel Overage • Cancel Shortage
Stock Code	<p>[Mandatory, Drop-Down]</p> <p>Select the stock code from the drop-down list.</p>
Denomination	<p>[Mandatory, Numeric, 10]</p> <p>Type the denomination of the inventory.</p>
Quantity	<p>[Mandatory, Numeric, 10]</p> <p>Type the quantity of the inventory.</p>
Face Value	<p>[Display]</p> <p>This field displays the face value of the inventory.</p> <p><i>Face value = denomination * quantity</i></p>

3. Select the inventory adjustment option and stock code from the drop-down list.
4. Enter the denomination and quantity.

Book or Cancel Overage/Shortage

Book or Cancel Overage/Shortage*

Teller Id : TSUBIT9999
TIL ID : 111 TIL Description : TSUBIT9999
Option : Book Overage
Stock Code : Debit Card
Denomination : 500
Quantity : 10
Face Value : 5000

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

5. Click the **Ok** button.
6. The system displays the message "Transaction Sequence number is ". Click the **OK** button.

3.11. 9030- Buy Cash From Teller

Using this screen branch teller can buy cash from another teller in the same branch. When the screen is opened, the Teller ID of the teller who has logged on is defaulted in the teller id field and is in disabled state. This transaction is always done with reference to a TIL ID.

Definition Prerequisites

- TIL01 - TIL ID Maintenance
- TIL02 - TIL Linkage Maintenance

Modes Available

Not Applicable

To Buy Cash from Teller

1. Type the fast path **9030** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Cash > Buy Cash from Teller**.
1. The system displays the **Buy Cash From Teller** screen.

Buy Cash From Teller

Buy Cash From Teller*

Teller Id : TSUBIT052000

TIL ID and Name : 131-TELLER03

From Teller : *

TIL ID and Name :

Currency : *

Total Required Cash : *

Narrative : *

Buy Cash From Teller

Card

Change Pin

Cheque

Cost Rate

FCY Change

Denomination

Instrument

Inventory

Pin Validation

Service Charge

Signature

Travellers Cheque

UDF

OK

Close

Clear

Field Description

Column Name	Description
Teller Id	[Alphanumeric, Text box] This field will default the Teller Id of the teller who is logged in (buying teller).
TIL ID and Name	[Alphanumeric, Text box] This field has TIL ID and the name linked to the logged in teller id (buying teller).
From Teller	[Alphanumeric, Drop-Down] This drop down contains only the tellers of same branch having TIL ID linked to them.
Currency	[Alphanumeric, Drop-Down] The drop down contains currencies.
Total Cash Required	[Numeric, Text box] Using this field the buying teller will input the amount required.
Narrative	[Alphanumeric, Text box] The system displays the default narration "Buy Cash From Teller". The teller can change the narration, if required.

2. Fill in the required details in the fields present on the screen.

Buy Cash From Teller

Buy Cash From Teller*

Teller Id : TIL ID and Name :

From Teller : * TIL ID and Name :

Currency : *

Total Required Cash : *

Narrative : *

Card	Change Pin	Cheque	Cost Rate	FCY Change	Denomination	Instrument	Inventory	Pin Validation	Service Charge	Signature	Travellers Cheque
------	------------	--------	-----------	------------	--------------	------------	-----------	----------------	----------------	-----------	-------------------

UDF OK Close Clear

3. Click the **OK** button. The System will display **Transaction number** on a Pop up.
4. Click on **OK** button. The transaction is completed successfully.

3.12. 9013 Buy Inventory From Teller

Using this screen branch teller can buy inventory from another teller in the same branch. When the screen is opened, the Teller ID of the teller who has logged on is defaulted in the teller id field and is in disabled state . This transaction is always done with reference to a TIL ID .

Definition Prerequisites

- TIL01 - TIL ID Maintenance
- TIL02 - TIL Linkage Maintenance

Modes Available

Not Applicable

To Buy Inventory from Teller

1. Type the fast path **9013** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Inventory > Buy Inventory from Teller**.
2. The system displays the **Buy Inventory From Teller** screen.

Field Description

Field Name	Description
Teller Id	[Alphanumeric, Text box] This field will default the Teller Id of the teller who is logged in (buying teller)
TIL ID and Name	[Alphanumeric, Text box] This field has TIL ID and the name linked to the logged in teller id (buying teller)
From Teller	[Alphanumeric, Drop Down] This drop down contains only the tellers of same branch having TIL ID linked to them
Stock Codes	[Alphanumeric, Drop Down] Select the Stock Code for the stock or inventory which you want to buy from the drop down list.
Quantity	[Numeric, Text box] Enter the Quantity of stocks which you want to buy.
Start No.	[Numeric, Text box] Type the start number in the stock series. This number onwards the stock has to be transferred.
End No.	[Display, Numeric, Text box] This field displays the end number of the series. The end number is calculated and generated by the system depending on the quantity and the start number specified. For example, If Quantity = 100 and Start No = 50 Then End No = 149
Face Value	[Display, Numeric, Text box] The field 'Face Value' displays the value of the inventory. Face Value = Denomination * Quantity.
Narrative	[Alphanumeric, Text box] The system displays the default narration "Buy Cash From Teller". The teller can change the narration, if required

5. Fill in the required details in the fields present on the screen.

9013 Buy Inventory From Teller

Buy Inventory From Teller*

Teller Id : TIL ID and Name :

Inventory Information :

From Teller : * TIL ID and Name :

Stock Code : *

Denomination : *

Series No : *

Quantity : *

Start No : *

End No :

Narrative : *

Card Change Pin **Cheque** Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

- Click on **OK** button.
- The System displays **Transaction number** on a Pop up, click on **OK** button.
- The transaction is completed successfully.

3.13. TIL01- TIL ID Maintenance

Using this screen a branch can define any number of TILs with TIL ID & name. A TIL ID can be defined anytime during the banking operations. This means, this can be a Day 0 activity for the branch or can be done post Day 0 also, as and when a new TIL ID is required.

This screen is used to perform TIL related operations such as linkage of TIL ID to the teller ID or de-linking of TIL ID from the teller ID and transfer of TIL from one teller to another of the same branch.

Definition Prerequisites

Not Applicable

Modes Available

Add, Modify, Delete, Cancel, Amend, Authorize, Inquiry. For more information on the procedures of every mode, refer to **Standard Maintenance Procedures**.

To define the TIL ID and Name

1. Type the fast path TIL01 and click Go or navigate through the menus to> Global Definitions > TIL > TIL ID Maintenance
2. The system displays the **TIL ID Maintenance** screen.

TIL ID Maintenance

TIL ID Maintenance*

TIL ID * TIL Description

Branch * Status

TIL Template Code Template Description

TIL Type

Remarks:

Record Details

Input By Authorized By Last Mnt. Date Last Mnt. Action Authorized ☐

☐ Add
 ☐ Modify
 ☐ Delete
 ☐ Cancel
 ☐ Amend
 ☐ Authorize
 ☒ Inquiry

Field Description

Field Name	Description
TIL ID	<p>[Display]</p> <p>This field displays the TIL ID.</p> <p>This code will be generated as per the masking defined at TIL template level.</p>
TIL Description	<p>[Alphanumeric, 40]</p> <p>Enter the name of the TIL ID which is selected to be inquired.</p>
Branch	<p>[Pick List, Alphanumeric, Three]</p> <p>Select the branch for which TIL ID is to be created from the pick list.</p> <p>All the TIL IDs which are existing in the system will be shown in the pick list.</p>
Status	<p>[Display]</p> <p>This field displays the status of the TIL ID.</p>
TIL Template Code	<p>[Mandatory, Pick List]</p> <p>Select the template code under which the TIL is to be created from the pick list.</p>
Template Description	<p>[Display]</p> <p>This field displays the description for the template.</p>
TIL Type	<p>[Display]</p> <p>This field displays the type of the TIL template defined.</p> <p>The values are:</p> <ul style="list-style-type: none"> • Teller • Vault • ATM

3. Type the TIL number.
4. Select the branch using the pick list.
5. Enter the TIL description in the respective field.
6. Click the **OK** button. You will be prompted with the following message " Record Added .. Authorization pending".

TIL ID Maintenance

TIL ID Maintenance*

TIL ID

9999000000000000000342

xxx

TIL Description*

TILMaintenance

Branch

9999

xxx

Status

Available

▼

TIL Template Code

1

xxx

Template Description

Noram1 TIL

TIL Type

Teller

▼

Remarks:

Record Details

Input By	Authorized By	Last Mnt. Date	Last Mnt. Action	Authorized
				<input type="checkbox"/>

☒ Add

☐ Modify

☐ Delete

☐ Cancel

☐ Amend

☐ Authorize

☐ Inquiry

UDF

Ok

Close

Clear

7. Authorize the Transaction using Fast path **TIL01** from supervisor Login. You will be prompted with "**Record Authorized ..**" message on successful Authorization".

3.14. TIL02- TIL ID Linkage Maintenance

Using this screen user will be able to link / de-link the TIL ID to teller ID or ATM Terminal ID. On selecting the teller ID radio button, the teller ID of the teller who is logged in will be defaulted in the Teller ID field and will be disabled. If a TIL is already linked to the teller, Option value as '**Delink TIL ID**' will be displayed in "**Option**" field which will be in a non editable state. Similarly, if option value is to link the TIL, 'Link TIL ID will be displayed and will be non editable state in this case, only TIL's available to the teller will be displayed in TIL ID pick list of the branch to which teller belongs and will be in a non editable state.

Definition Prerequisites

- TIL01 - TIL ID Maintenance

Modes Available

- Not Applicable

To Link / De-Link the TIL ID

1. Type the fast path **TIL02** and click **Go** or navigate through the menus to **Global Definitions> Internal Transactions> TIL> TIL Linkage Maintenance**
2. The system will display **TIL Linkage Maintenance** screen.

TIL ID Linkage Maintenance

[illegible]

Field Description

Column Name	Description
Teller Id	[Mandatory, Radio Button] Select the option whether to link the TIL to teller or ATM Terminal ID.
ATM Terminal Id	[Mandatory, Radio Button] Select the option whether to link the TIL to teller or ATM Terminal ID.
Teller Id	[Optional, Pick List] Select the teller ID for whom TIL related operations are to be performed from the pick list. This field will be enabled if the Teller ID radio button is selected.

Column Name	Description
ATM Terminal Id	<p>[Conditional, Alphanumeric, Pick List]</p> <p>Select the ATM terminal Id from the pick list or enter it.</p> <p>The list has the values maintained in ATM Acquirer POS Id Maintenance (FP: ATM02) option. The ATM terminal ID already linked will not be displayed.</p> <p>This field is enabled if the ATM Terminal ID radio button is selected.</p>
Option	<p>[Conditional, Drop-Down]</p> <p>Select the type of TIL operation to be performed from the drop-down list.</p> <p>The options are:</p> <ul style="list-style-type: none"> • Link • Delink for Submit • Delink for Transfer
TIL Id	<p>[Mandatory, Numeric, Pick List]</p> <p>Select the TIL ID from the pick list.</p> <p>This field will have TIL IDs, If a TIL is already linked, the TIL No. field will display the linked TIL No. to the Teller Id and will allow to delink the TIL. In case of no TIL is linked, teller will be allowed to link a TIL from the pick list.</p>
TIL Description	<p>[Alphanumeric]</p> <p>This field displays the corresponding TIL name of the selected TIL number.</p>

3. Select the appropriate option by clicking on the respective **Radio button**. The **teller ID** field will default the Teller Id of the teller who is logged in.
4. On selecting the **ATM Terminal ID**, the ATM terminal ID field will be enabled and values will be displayed accordingly in the pick list.
5. Select the **TIL ID** using the pick list.
6. Click the **OK** button, the system will prompt you with a "Transaction completed successfully" message on a pop.

TIL Linkage Maintenance - Cash

TIL Linkage Maintenance*

☐ Teller ID
 ☒ ATM Terminal ID

Teller ID:

ATM Terminal ID:

Option*:

TIL ID:

TIL description*:

Cash | Inventory

Currency	Total Counted Cash	Cash Available	Overage/Shortage
AUD	0.00	0.00	0.00
EGP	0.00	0.00	0.00
CNY	0.00	0.00	0.00
HKD	0.00	0.00	0.00
JPY	0.00	0.00	0.00
KRW	0.00	0.00	0.00
GBP	0.00	0.00	0.00
USD	0.00	0.00	0.00
EUR	0.00	0.00	0.00

Card | Change Pin | Cheque | Cost Rate | FCY Change | Denomination | Instrument | Inventory | Pin Validation | Service Charge | Signature | Travellers Cheque

UDF | OK | Close | Clear

Field Description

Column Name	Description
Currency	[Display] This column displays the currencies in which the bank deals.
Total Cash	[Mandatory, Numeric, 13, Two] Type the total cash for a particular currency, physically present with the teller, at the end of the current posting date. This amount should match with the cash displayed in the Cash Available column. If there is a mismatch in the amounts, the teller cannot close the batch.

Column Name	Description
Cash Available	<p>[Display]</p> <p>This column displays the amount for a particular currency, which is available with the teller at the end of the current posting date.</p> <p>This amount is calculated by the system and depends on the transactions carried out by the teller on the current posting date.</p>
Overage/Shortage	<p>[Display]</p> <p>This column displays the difference in the amount between the total cash and the available cash with the teller, at the end of the current posting date.</p> <p>Based on this difference the overage or the shortage amount is displayed.</p> <p>An overage indicates that the physical cash with the teller is more than the available cash as calculated by the system.</p> <p>A shortage indicates that the available cash calculated by the system, is more than the physical cash present with the teller.</p>

7. Click the **Inventory** Tab to view the Opening Inventory

TIL Linkage Maintenance - Inventory

TIL Linkage Maintenance*

☒ Teller ID ☐ ATM Terminal ID

Teller ID:

ATM Terminal ID:

Option:

TIL ID*:

TIL description*:

Cash **Inventory**

Stock Code	Description	Denomination	Total Quantity	Face Value	Available Quantity	Overage/Shortage	Booked Overage	Booked Shortage
731	CASH CHEQUE	1	88	88	88	0	0	0
732	FUND TRANSFER CHEQUE	1	100	100	100	0	0	0
734	NORMAL PASSBOOK FOR CASH	1	97	97	97	0	0	0
736	CORPORATE DEPOSIT CERTIFICATE	1	99	99	99	0	0	0
737	RETAIL DEPOSIT PROOF CERTIFICATE	1	96	96	96	0	0	0
760	CORPORATE DEPOSIT PROOF	1	99	99	99	0	0	0

1 / 1

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

Field Description

Column Name	Description
Stock Code	[Display] This column displays the inventory code.
Description	[Display] This column displays a short description for the inventory.
Denomination	[Display] This column displays the denomination of the inventory available with the teller at the end of the current posting date.
Total Quantity	[Mandatory, Numeric, 10] Type the quantity of stock available with the teller. This value should match with the count displayed in the Available Quantity column. If there is a mismatch, the teller cannot close the batch.
Face Value	[Display] This column displays the value of the stock. <i>Face Value = Quantity * denomination.</i>
Available Quantity	[Display] This column displays the quantity of stock available in the system.
Overage/Shortage	[Display] This column displays the quantity of stock that is booked as overage or shortage.
Booked Overage	[Display] This column displays the quantity of stock which is booked as overage on the previous day in the system.
Booked Shortage	[Display] This column displays the quantity of stock which is booked as shortage on the previous day in the system.

8. Click the **OK** button. The system displays the message "transaction completed successfully".

4. Other Transactions

The tellers and supervisors of the bank can perform ancillary activities in **FLEXCUBE Retail**. This system facilitates the bank in transferring the CASA account (single account or multiple accounts) from one branch to another branch, changing the ownership of unauthorized batch and printing spooled documents.

4.1. TIL10- TIL Template Maintenance

Using this screen user will be able define various TIL templates. The TIL templates having lower and upper cash retention limits for each currency of the TIL, separate TIL templates based on TIL types – Teller, Vault and ATM.

Definition Prerequisites

Not Applicable

Modes Available

Not Applicable

To add the TIL template

1. Type the fast path **TIL10** and click **Go** or navigate through the menus to **Global Definitions> Internal Transactions> TIL> TIL Template Maintenance**
2. The system will display **TIL Template Maintenance** screen.

TIL Template Maintenance

TIL Template Maintenance*

TIL Template Code Template Description
TIL Type TIL ID Mask*

Currency	Lower Retention Limit	Upper Retention Limit	Delete

Remarks:

Record Details

Input By Authorized By Last Mnt. Date Last Mnt. Action Authorized ☐

☐ Add By Copy ☐ Add ☐ Modify ☐ Delete ☐ Cancel ☐ Amend ☐ Authorize ☒ Inquiry

UDF Ok Close Clear

Field Description

Column Name	Description
TIL Template Code	[Mandatory, Numeric, Three] Enter the template code to be assigned.
Template Description	[Mandatory, Alphanumeric, 120] Enter the description for the template.
TIL Type	[Mandatory, Drop-Down] Select the type of the TIL template defined from the drop-down list. The options are – <ul style="list-style-type: none"> • Teller • Vault • ATM
TIL ID Mask	[Mandatory, Pick List] Select the TIL ID masking from the pick list. The mask can be as: <ul style="list-style-type: none"> • BBBBNNNNNNNNNNNNNNNNNN (first 4 digits branch code and next 16 digits running serial number) • NNNNNNNNNNNNNNNNNNNNNN (20 digits running serial number)
Currency	[Mandatory, Drop-Down] Select the currency for which the cash retention limit is to be defined.
Lower Retention Limit	[Mandatory, Numeric, 13, Two] Enter the lower cash retention limit for the specified currency. If the cash position reaches below this limit, the user will be prompted to maintain the same.
Upper Retention Limit	[Mandatory, Numeric, Three] Enter the upper cash retention limit for the specified currency. If the cash position reaches above this limit, the user will be prompted to maintain the same.
Delete	[Optional, Toggler] Click the toggle status to Y to delete the field. The default value is N.

3. Click the **Add** button.
4. Enter the TIL Template code and press the **<Tab>** key.
5. Select the **TIL Type** from the drop-down list.

TIL Template Maintenance

TIL Template Maintenance*

TIL Template Code: 322 Template Description: Template Maintenance
 TIL Type*: Teller TIL ID Mask: BBBBBBBBBBBBBBBBBB

Currency	Lower Retention Limit	Upper Retention Limit	Delete

Remarks:

Record Details

Input By	Authorized By	Last Mnt. Date	Last Mnt. Action	Authorized
				<input type="checkbox"/>

☐ Add By Copy
 ☒ Add
 ☐ Modify
 ☐ Delete
 ☐ Cancel
 ☐ Amend
 ☐ Authorize
 ☐ Inquiry


UDF Ok Close Clear

Field Description


Column Name Description

Currency	[Mandatory, Drop-Down] Select the currency for which the cash retention limit is to be defined.
Lower Retention Limit	[Mandatory, Numeric, 13, Two] Enter the lower cash retention limit for the specified currency. If the cash position reaches below this limit, the user will be prompted to maintain the same.
Upper Retention Limit	[Mandatory, Numeric, Three] Enter the upper cash retention limit for the specified currency. If the cash position reaches above this limit, the user will be prompted to maintain the same.

Delete [Optional, Toggler]
Click the toggle status to Y to delete the field.
The default value is N.

6. Click the **Add**  button.
7. Enter the other relevant details.

TIL Template Maintenance



TIL Template Maintenance*

TIL Template Code: 322
Template Description: nplate Maintenance
TIL Type: Teller
TIL ID Mask: BBBBNNNNNNNNNNNNNNNN

Currency	Lower Retention Limit	Upper Retention Limit	Delete
CNY	0.00	999,999,999.99	N
EUR	0.00	999,999,999.99	N

Remarks:

Record Details

Input By: Authorized By: Last Mnt. Date: Last Mnt. Action: Authorized: ☐

☐ Add By Copy ☒ Add ☐ Modify ☐ Delete ☐ Cancel ☐ Amend ☐ Authorize ☐ Inquiry

UDF Ok Close Clear

8. Click the **OK** button. The system displays the message "Record Added.....Authorization Pending".

4.2. 4501 - Centralised Authorisation

Centralised authorization is a security enhancing setup which can be enabled in **Oracle FLEXCUBE** for providing additional authorizations when predefined reasons are encountered in online transactions by a group of supervisors, preferably from those located centrally.

This level of authorization is subsequent to and in addition to the local/remote authorization which would have been provided for the transaction to confirm the overrides.

The predefined reasons are defined in the branch database in an internal table called ba-auth-reason-mast table.

Centralised authorization is done by a specific transaction which can be accessed only by certain supervisors as identified in the Security Management System (SMS) setup. Supervisors accessing this transaction can identify the transaction(s) to be authorised by using the from branch, transaction code, customer id and account number combination.

The centralised authorization process is divided into the following steps namely:

If auto-authorization is disabled:

Step	Activity By	Activity Description
A	Teller	Teller performs online transaction from the branch. If system encounters conditions requiring local/remote authorization, transaction will proceed to step B. If system does not encounter any conditions requiring local/remote authorization but encounters centralised authorization requirement, system will proceed to step D.
B	Supervisor	Supervisor approves the transaction using local authorization or remote authorization. If local authorization is provided, system proceeds for further processing.
C	Teller	Teller resubmits the approved transaction from the Electronic Journal, for transactions sent for remote authorization. System encounters reasons requiring central authorization. Teller sends the transaction for central authorization.
D	Supervisor	Supervisor access the central authorization transaction and authorizes the transaction waiting for authorization.
E	Teller	Teller resubmits the approved transaction from the Electronic Journal and completes the transaction.

If auto-authorization is enabled:

Step	Activity By	Activity Description
A	Teller	Teller performs online transaction from the branch. If system encounters conditions requiring local/remote authorization, transaction will proceed to step B. If system does not encounter any conditions requiring local/remote authorization but encounters centralised authorization requirement, system will proceed to step D.
B	Supervisor	Supervisor approves the transaction using local authorization or remote authorization. If local authorization is provided, system proceeds for further processing.
C	Teller	System encounters reasons requiring central authorization. Teller sends the transaction for central authorization.
D	Supervisor	Supervisor access the Central authorization transaction and authorizes the transaction waiting for authorization.

At Local Branch:

The supervisor authorises the transaction done by the teller locally or remotely. For more information on Local and Remote authorizations refer to **Local Authorization** and **Remote Authorization** earlier in this chapter.

Definition Prerequisites

Not Applicable

Modes Available

Not Applicable

To perform centralised authorisation

1. Type the fast path **4501** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Authorisation > Centralised Authorisation**.
2. The system displays the **4501 - Centralised Authorisation** screen.

Centralised Authorisation

Centralised Authorisation

From Branch : To Branch :

Mnemonic : ...

Customer Id :

Account No :

Teller Id :

Txn Date	TxnTime	Branch	UserID	SeqNo	Mnem	Cust Id	Account No	Description	Ccy	Amount	State	Authorizer
----------	---------	--------	--------	-------	------	---------	------------	-------------	-----	--------	-------	------------

Fetch Cancel

Field Description

Field Name	Description
From Branch	[Optional, Numeric, Four] Type the From branch.
To Branch	[Optional, Numeric, Four] Type the To branch.
Mnemonic	[Optional, Pick List] Select the task code from the pick list.
Customer Id	[Optional, Numeric, 10] Type the customer ID.
Account No	[Optional, Numeric, 16] Type the account number.
Teller Id	[Optional, Alphanumeric] Type the id of the teller whose records are to be authorised.

Column Name	Description
Txn Date	[Display] This column displays the transaction date.
Txn Time	[Display] This column displays the transaction time.
Branch	[Display] This column displays the branch code.
User Id	[Display] This column displays the user id.
SeqNo	[Display] This column displays the sequence number.
Mnem	[Display] This column displays the mnemonic code.
Cust Id	[Display] This column displays the customer id.
Account No	[Display] This column displays the account number.
Description	[Display] This column displays the account description.
Ccy	[Display] This column displays the account currency.
Amount	[Display] This column displays the transaction amount.
State	[Display] This column displays the transaction status.
Authorizer	[Display] This column displays the authorizer id.

3. Enter the details based on which a search is to be performed.
4. Click the **Fetch** button. The system displays all the transactions sent for authorization based on the filter criteria.

Centralised Authorisation

Centralised Authorisation

From Branch :

To Branch :

Mnemonic :

...

Customer Id :

Account No :

Teller Id :

Txn Date	TxnTime	Branch	UserID	SeqNo	Mnem	Cust Id	Account No	Description	Ccy	Amount	State	Authorizer
----------	---------	--------	--------	-------	------	---------	------------	-------------	-----	--------	-------	------------

Fetch

Cancel

5. Click the transaction to view the transaction details.
6. The system displays the transaction details screen. The supervisor cannot modify any details on the screen.
7. Click the **Grant** button to authorize the transaction.
8. Click the **Deny** button to deny authorization of the transaction.
9. The system displays the **Authorization Reasons** screen.
10. Select the reason from the drop-down list and type the comments.
11. Click the **Ok** button.

4.3. BA995 - Single Account Transfer

Using this option, a bank can transfer a CASA/TD/Loan account from one branch to another, if the customer initiates the transfer. An existing sub-branch/outlet is updated to a branch/sub-branch. The account number of the effected accounts will not change but the branch to which the account reports will change

It is not possible to transfer an account from one product to another product. Also account transfer will be disallowed for the accounts which are members of the group linked in the **Group Accounts Maintenance** (Fast Path: CHM24) option.

Definition Prerequisites

- BAM03 - Branch Master Maintenance
- The branch and transfer branch product should be the same.

Modes Available

Add By Copy, Add, Modify, Delete, Cancel, Amend, Authorize, Inquiry. For more information on the procedures of every mode, refer to **Standard Maintenance Procedures**.

To transfer a single account from one branch to another

1. Type the fast path **BA995** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Others > Single Account Transfer**.
2. The system displays the **Single Account Transfer** screen.

Single Account Transfer

Field Description

Field Name	Description
Account Number	<p>[Mandatory, Numeric, 16]</p> <p>Type the account number that has to be transferred to another branch.</p> <p>The account name is populated in the corresponding field.</p>
Account Status	<p>[Display]</p> <p>This field displays the account status.</p>
Product Code	<p>[Display]</p> <p>This field displays the product code under which the account opened.</p>
Branch Name	<p>[Display]</p> <p>This field displays the name of the home branch where the account is currently held.</p>

Field Name	Description
Transfer Branch Name	[Mandatory, Pick List] Select the name of the branch, to which the account is to be transferred, from the pick list.

- Click the **Add** button.
- Enter the account number and press the **<Tab>** key.
- Select the branch name from the pick list.

Single Account Transfer

Single Account Transfer*

Account Number : 000000004796 RAMPRAJ

Account Status : Regular Account

Product Code : 10-PG59 CURRENT ACCOUNT

Branch Name : HO Head Office

Transfer Branch Name : 700 Jakarta

Record Details

Input By Authorized By Last Mint. Date Last Mint. Action Authorized

☐ Add By Copy ☒ Add ☐ Modify ☐ Delete ☐ Cancel ☐ Amend ☐ Authorize ☐ Inquiry UDF Ok Close Clear

- Click the **Ok** button.
- The system displays the message "Record Added...Authorization Pending...". Click the **Ok** button.
- The single account transfer record is added once the record is authorized.

4.4. BA999 - Bulk Account Transfer

Using this option the bank can transfer all **Oracle FLEXCUBE** accounts across products from one branch to another branch when a branch is closed or merged. This screen allows an existing sub-branch/outlet to merge with another existing sub-branch/outlet. Multiple existing sub-branches/outlets can also merged with another existing sub-branch/outlet. Bulk account transfer can be used for each of the multiple branches intended to be merged. (**FLEXCUBE** currently do not support bulk merging of branches). An existing sub-branch/outlet is updated to a branch/sub-branch. Part of individual accounts in an existing sub-branch/outlet is moved to a new or existing sub-branch/outlet. The account numbers of the affected accounts do not change but the branch to which they report to get changed.

It is not possible to transfer accounts from one product to another. This option can also be used when banks decide to open special type of branches catering to specific customer needs and decides to transfer the existing accounts from other branches to the new branch.

This screen also supports the transfer of Loan accounts to the destination branch.

A validation is provided to check whether the products available in the old branch is also available in the new branch, if not those products will be automatically linked to the new branch. Bank ensures that:

- No new products are linked to the old branch after the branch merger.
- Other parameters related with the old branch except branch product cross reference will not be updated to the destination branch.
- No customer or account opening happens in that branch.
- It is not allowed to be merged if the branch has child branches. Child branches should be delinked from the branch first.

Definition Prerequisites

- BAM03 - Branch Master Maintenance

Modes Available

Add By Copy, Add, Modify, Delete, Cancel, Amend, Authorize, Inquire. For more information on the procedures of every mode, refer to **Standard Maintenance Procedures**.

To add the bulk account transfer

1. Type the fast path **BA999** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Others > Bulk Account Transfer**.
2. The system displays the **Bulk Account Transfer** screen.

Bulk Account Transfer

Field Description

Field Name	Description
Transfer Date	<p>[Mandatory, Pick List, dd/mm/yyyy]</p> <p>Select the date when the bulk account will be transferred from the pick list.</p> <p>By default, the system displays the current date as the transfer date.</p>
Branch Name	<p>[Mandatory, Pick List]</p> <p>Select the branch from where all the accounts across the products have to be transferred to another branch from the pick list.</p> <p>The name for the selected branch code is displayed in the adjacent field.</p>
Transfer Branch Name	<p>[Mandatory, Pick List]</p> <p>Select the branch to which all the accounts across the products have to be transferred from the pick list.</p> <p>The name for the selected branch code is displayed in the adjacent field.</p>

- Click the **Add** button.

4. Enter the transfer date.
5. Select the branch name and the transfer branch name from the pick list.

Bulk Account Transfer

Bulk Account Transfer*

Transfer Date : 15/02/2008

Branch Name : 700 Jakarta

Transfer Branch Name : 9999 HO

Record Details

Input By : Authorized By : Last Mnt. Date : Last Mnt. Action : Authorized :

☐ Add By Copy ☒ Add ☐ Modify ☐ Delete ☐ Cancel ☐ Amend ☐ Authorize ☐ Inquiry

UDF Ok Close Clear

6. Click the **Ok** button.
7. The system displays the message "Record Added". Click the **OK** button.

4.5. 5514 - Change Data Entry Batch User

Using this option the ownership of an unauthorised batch can be changed from one teller to another, as system does not allow tellers to work on batches not owned by them.

This is done when the original teller who had done the transaction is not available and the batch needs to be modified. In such situations, this option is used to transfer the ownership of the unauthorised batch to another teller or user.

The owner of the Voucher Entry branch cannot be changed by using this option.

Definition Prerequisites

- Branch batch to be opened and teller batch opened for the change.

Modes Available

Not Applicable

To change the data entry batch user

1. Type the fast path **5514** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Data Entry > Change Data Entry Batch User**.
2. The system displays the **Change Data Entry Batch User** screen.

Change Data Entry Batch User

Change Data Entry Batch User*

Batch Type :

Batch Number :

Current Teller Id :

New Teller Id :

Card Change Pin Cheque Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

Field Description

Field Name	Description
Batch Type	<p>[Mandatory, Pick List]</p> <p>Select the type of data entry batch that needs to be inquired from the pick list.</p> <p>The options are:</p> <ul style="list-style-type: none"> • Consolidated Cheque Deposit • ICC Data Entry • Inward Clearing Data entry • MICR-Serial No Xref maintenance • OCC Data Entry • Outward Clearing Cheque Data Entry • Post Dated Cheque Batch Data Entry <p>These options are taken from a static pick list.</p>
Batch Number	<p>[Mandatory, Pick List]</p> <p>Select the appropriate batch number, which needs to be transferred to the new teller from the pick list.</p>
Current Teller Id	<p>[Display]</p> <p>This field displays the ID of the current teller.</p> <p>This is automatically retrieved by the system upon entering the batch number. This shows the current maker of the batch from whom the batch needs to be transferred.</p>
New Teller Id	<p>[Mandatory, Drop-Down]</p> <p>Select the appropriate teller ID to which the batch is to be transferred from the drop-down list.</p>

3. Select the batch type and batch number from the pick list.
4. Select the new teller ID from the drop-down list.

Change Data Entry Batch User

Change Data Entry Batch User*

Batch Type : Consolidated Cheque Deposit ...

Batch Number : 101 ...

Current Teller Id : TDEEPAKM

New Teller Id : TPAY

Card	Change Pin	Cheque	Cost Rate	Denomination	Instrument	Inventory	Pin Validation	Service Charge	Signature	Travellers Cheque
------	------------	--------	-----------	--------------	------------	-----------	----------------	----------------	-----------	-------------------

UDF OK Close Clear

5. Click the **OK** button.
6. The system displays the teller changed message. Click the **OK** button.

4.6. 5515 - List Batch Status

Using this option you can view the status of all data entry batches, except Voucher Entry batches, done by the various tellers in that branch for the current posting date.

A teller can view the status of all batches owned by him. A supervisor will be able to check the status of all batches owned by tellers under his preview. The system provides information on teller ID, batch number, batch status, count, document number and the total transaction amount.

Definition Prerequisites

- Teller batches to be opened.

Modes Available

Not Applicable

To list the batch status

1. Type the fast path **5515** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Data Entry > List Batch Status**.
2. The system displays the **List Batch Status** screen.

List Batch Status

List Batch Status *

Batch Type :

...

Teller Id :

...

Batch Number :

...

SrNo	TellerId	BatchNum	Batch Status	Count	DocNo	Currency	Amount
------	----------	----------	--------------	-------	-------	----------	--------

Card

Change Pin

Cheque

Cost Rate

Denomination

Instrument

Inventory

Pin Validation

Service Charge

Signature

Travellers Cheque

UDF

OK

Close

Clear

Field Description

Field Name	Description
Batch Type	<p>[Mandatory, Pick List]</p> <p>Select the type of data entry batch that needs to be inquired from the pick list.</p> <p>The options are:</p> <ul style="list-style-type: none"> • Consolidated Cheque Deposit • ICC Data Entry • Inward Clearing Data entry • MICR-Serial No Xref maintenance • OCC Data Entry • Outward Clearing Cheque Data Entry • Post Dated Cheque Batch Data Entry • Consolidated DD / BC Issue <p>These options are taken from a static pick list.</p>
Teller Id	<p>[Optional, Pick List]</p> <p>Select the teller ID for whom the status of data entry batches needs to be inquired from the pick list.</p>
Batch Number	<p>[Optional, Pick List]</p> <p>Select the number of the batch, which has to be inquired from the pick list.</p> <p>The system populates the batch numbers based on the selected teller ID.</p>
Column Name	Description
SrIno	<p>[Display]</p> <p>This column displays the running serial number generated by the system.</p>
TellerId	<p>[Display]</p> <p>This column displays the user ID of the teller who has performed the data entry batch.</p>
BatchNum	<p>[Display]</p> <p>This column displays the number of the batch depending on the batch type selected.</p>

Column Name	Description
Batch Status	<p>[Display]</p> <p>This column displays the status of the selected batch.</p> <p>The options are:</p> <ul style="list-style-type: none"> • Authorised • Validated • Unauthorised • Reversed
Count	<p>[Display]</p> <p>This column displays the count denotes the total number of instruments entered in the batch.</p>
DocNo	<p>[Display]</p> <p>This column displays the document number or the header number associated with the consolidated batch.</p> <p>This number is automatically generated by the system while entering the header details and is attached to the batch.</p>
Currency	<p>[Display]</p> <p>This column displays the transaction currency of the batch.</p>
Amount	<p>[Display]</p> <p>This column displays the total transaction amount of the batch.</p>

3. Select the batch type from the pick list.
4. Enter the other relevant details.
5. Click the **Ok** button.
6. The system displays the batch status.

List Batch Status

List Batch Status*

Batch Type : Consolidated Cheque Deposit

Teller Id :

Batch Number :

SrNo	TellerId	BatchNum	Batch Status	Count	DocNo	Currency	Amount
1	TSUNNY	31	Reversed	2	00024200	USD	1500
2	TSUNNY	34	Reversed	2	00024300	USD	100
3	TDEEPAKM12	11	AUTHORIZED	3	00060861000	INR	42015
4	TDEEPAKM12	12	AUTHORIZED	6	00060861300	INR	78000
5	TDEEPAKM560	22	AUTHORIZED	3	00060941000	INR	6687
6	TDEEPAKM11	26	AUTHORIZED	3	00060781900	INR	100000
7	TDEEPAKM560	30	AUTHORIZED	2	320456094	INR	8809
8	TDEEPAKM11	30	AUTHORIZED	2	221336078	INR	4487
9	TDEEPAKM560	31	AUTHORIZED	2	360456094	INR	11089

CardChange PinChequeCost RateDenominationInstrumentInventoryPin ValidationService ChargeSignatureTravellers Cheque

UDFOKCloseClear

7. Click the **Close** button.

4.7. 9800 - Print Spooled Documents

Using this option the spooled documents can be printed. These documents pertain to the branch transactions performed by a teller during the day.

The spooled document is printed in the following situations:

- If the teller wants to spool all documents, and then print them together at a later time during the day
- If the customer asks for another copy of the document
- If the supervisor wants to print a document belonging to a particular teller

Definition Prerequisites

Not Applicable

Modes Available

Not Applicable

To print spooled documents

1. Type the fast path **9800** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Reports > Print Spooled Documents**.
2. The system displays the **Print Spooled Documents** screen.

Print Spooled Documents

Print Spooled Documents*

Teller ID : TKATDARE Posting Date : 15/01/2004

Seq No	Doc Num	Desc	Doc Date	Num Print	Doc Type	Print/View
--------	---------	------	----------	-----------	----------	------------

0 /0

Card Change Pin Cheque Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque << >> Print View UDF Get Close Clear

Field Description

Field Name	Description
Teller Id	<p>[Display]</p> <p>This field displays the ID of the teller who has logged in.</p> <p>The system displays the documents spooled by the teller who has logged in.</p> <p>In case of a supervisor login, the system displays the spooled documents of any teller associated under his/her supervision.</p> <p>This field is editable, in case of a supervisor login.</p>
Posting Date	<p>[Mandatory, Pick List, dd/mm/yyyy]</p> <p>Select the posting date, for which the teller needs to print the spooled documents, from the pick list.</p> <p>By default, the system displays the current posting date.</p>
Column Name	Description
SeqNo	<p>[Display]</p> <p>This column displays the sequence number generated by the system while performing the actual transaction.</p>
Doc Num	<p>[Display]</p> <p>This column displays the number of documents to be printed.</p>
Desc	<p>[Display]</p> <p>This column displays the description given to the document.</p> <p>For example, a receipt for payment received.</p>
Doc Date	<p>[Display]</p> <p>This column displays the date of the document.</p> <p>It is normally the transaction posting date.</p>
Num Print	<p>[Display]</p> <p>This column displays the number of copies of the document that need to be printed.</p>
Doc Type	<p>[Display]</p> <p>This column displays the document type.</p> <p>Different numbers are given for different types of documents based on their description.</p>
Print/View	<p>[Optional, Check Box]</p> <p>Select the Print/View check box to print/view the document.</p>

3. Select the posting date from the pick list.
4. Click the **Get** button.

- The spooled document details are displayed on the screen.

Print Spooled Documents

Print Spooled Documents*

Teller ID : TKATDARE Posting Date : 20/03/2008

Seq No	Doc Num	Desc	Doc Date	Num Print	Doc Type	Print/View
10	1	Receipt	20/03/2008	0	2	<input type="checkbox"/>

1 / 1

Card Change Pin iCheque Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

<< >> Print View UDF Get Close Clear

- Select the check box against the relevant transaction, and click the **Print** or **View** button depending on whether you want to print or view the document/report.
- Click the **Close** button.

4.8. BA123 - Payment Verification Mandate Maintenance*

Using this option you can maintain payment verification mandate within the system and warn the teller to verify the transactions' credentials while doing the large amount of debit transactions. You can ascertain that for transactions exceeding a certain amount, payment verification is always done.

Definition Prerequisites

- 8053 - Customer Addition
- 8054 - Time Deposit Account Opening

Modes Available

Add, Modify, Delete, Cancel, Amend, Authorize, Inquiry. For more information on the procedures of every mode, refer to **Standard Maintenance Procedures**.

To add new payment verification mandate

1. Type the fast path **BA123** and click **Go** or navigate through the menus to **Global Definition > Master > Payment Verification Mandate Maintenance**.
2. The system displays the **Payment Verification Mandate Maintenance** screen.

Payment Verification Mandate Maintenance

Payment Verification Mandate Maintenance*

Account Number :

Payment Verification Mandate Details

Payment Verification Amount :

Contact Person 1 :

Contact Person 1 Telephone No :

Contact Person 2 :

Contact Person 2 Telephone No :

Remarks:

Record Details				
Input By	Authorized By	Last Mnt. Date	Last Mnt. Action	Authorized
				<input type="checkbox"/>

☐ Add By Copy
 ☐ Add
 ☐ Modify
 ☐ Delete
 ☐ Cancel
 ☐ Amend
 ☐ Authorize
 ☒ Inquiry

UDF Ok Close Clear

Field Description

Field Name	Description
Account Number	<p>[Mandatory, Pick List, Numeric, 16]</p> <p>Select the account number of CASA/RD/TD account of the customer for which the payment verification mandate has to be setup from the pick list or enter it.</p> <p>It should be a valid CASA/RD/TD account.</p>
Payment Verification Mandate Details	
Payment Verification Amount	<p>[Mandatory, Numeric, 13, Two]</p> <p>Type the amount above which the verification needs to be performed.</p> <p>Payment verification amount mandate will always be maintained in the account currency.</p>
Contact Person 1	<p>[Optional, Alphanumeric, 120]</p> <p>Type the name of the primary contact person to be contacted to confirm the payment.</p>
Contact Person 1 Telephone No.	<p>[Optional, Alphanumeric, 30]</p> <p>Type the telephone number of the primary contact person.</p>
Contact Person 2	<p>[Optional, Alphanumeric, 120]</p> <p>Type the name of the secondary contact person to be contacted to confirm the payment.</p>
Contact Person 2 Telephone No.	<p>[Optional, Alphanumeric, 30]</p> <p>Type the telephone number of the secondary contact person.</p>

3. Click the **Add** button.
4. Select the account number of the customer from the pick list.
5. Enter the payment verification amount and other relevant information.

Payment Verification Mandate Maintenance

Payment Verification Mandate Maintenance*

Account Number : 100020000000059

Payment Verification Mandate Details

Payment Verification Amount : 10,000.00

Contact Person 1 : John Thames

Contact Person 1 Telephone No : 77822344444

Contact Person 2 : Richard Garvell

Contact Person 2 Telephone No : 454323232332

Remarks:

Record Details

Input By	Authorized By	Last Mnt. Date	Last Mnt. Action	Authorized
				<input type="checkbox"/>

☐ Add By Copy
 ☒ Add
 ☐ Modify
 ☐ Delete
 ☐ Cancel
 ☐ Amend
 ☐ Authorize
 ☐ Inquiry

- Click the **Ok** button.
- The system displays the message "Record Added...Authorisation Pending.". Click the **Ok** button.

4.9. LN032-Subsidy Payments Instructions

Using this screen you can maintain and define the loan accounts which are linked to a particular government subsidy account. The purpose of this screen is to maintain the mapping / cross reference between the end borrower's loan account with the subsidy account of the government which will be used for subsidy payment purposes.

Definition Prerequisites

Not Applicable

Modes Available

Add, Modify, Delete, Inquiry. For more information on the procedures of every mode, refer to **Standard Maintenance Procedure**.

To add billing details of loan accounts

1. Type the fast path **LN032** and click **Go** or navigate through the menus to **Global Definition > Transaction Processing > Customer transaction> Subsidy Payments Instructions**.
2. The system displays the **Subsidy Payments Instructions** screen.

Subsidy Payments Instructions

Subsidy Payments Instructions*

Account No : *

Customer Name :

Branch :

Product :

Currency :

Remitter Account No :

Branch :

Customer Name :

Currency :

Product :

Remarks:

Record Details

Input By	Authorized By	Last Mnt. Date	Last Mnt. Action	Authorized
				<input type="checkbox"/>

☐ Add By Copy
 ☐ Add
 ☐ Modify
 ☐ Delete
 ☐ Cancel
 ☐ Amend
 ☐ Authorize
 ☒ Inquiry

UDF

Ok

Close

Clear

Field Description

Field Name	Description
Account Number	<p>[Numeric, Text Box, Sixteen]</p> <p>The teller will input the loan account number in this field against which the mapping for the government subsidy needs to be maintained.</p>
Customer Name	<p>[Alpha Numeric, Text Box, Twenty]</p> <p>Type the amount that the teller needs to sell to the vault.</p> <p>The teller position gets updated as soon as the transaction is complete. If the amount exceeds the maximum limit that the teller is allowed to retain with him/her, the system prompts the teller to sell the excess cash to the vault. This can be done immediately or before the teller batch is closed for the posting date.</p>
Branch	<p>[Alphanumeric, Text box]</p> <p>This field will display the account branch.</p>
Product	<p>[Numeric, Text box]</p> <p>This field will display the product code of the account.</p>
Currency	<p>[Alphabetic, Text box]</p> <p>This field will display the currency of the account / product .</p>
Remitter Account No	<p>[Numeric, Text box]</p> <p>This field will display the subsidy CASA , the teller can modify the field, if required. The government subsidy CASA will be inputted by the teller.</p>
Branch	<p>[Alphabetic, Text box]</p> <p>This field will display the Subsidy CASA account.</p>
Currency	<p>[Alphabetic, Text box]</p> <p>This field will display Subsidy CASA customer name .</p>
Product	<p>[Numeric, Text box]</p> <p>This field will display the Product code of subsidy CASA .</p>

3. Enter the account number and press the **<Tab>** key.
4. Enter the relevant information.

Subsidy Payments Instructions

Subsidy Payments Instructions*

Account No : * 0010000500001834 Customer Name : MUSTUFA YUSUF GARI
 Branch : 1000 Product : 70000 Index Level - A
 Currency : RMB

Remitter Account No :

Branch : Customer Name :
 Currency : Product :

Remarks:

Record Details				
Input By	Authorized By	Last Mnt. Date	Last Mnt. Action	Authorized
				<input type="checkbox"/>

☐ Add By Copy ☒ Add ☐ Modify ☐ Delete ☐ Cancel ☐ Amend ☐ Authorize ☐ Inquiry

UDF OK Close Clear

5. Click the **Ok** button.
6. The system displays the message "Authorization Required. Do You Want to Continue". Click the **Ok** button.
7. The system displays the **Authorization Reason** screen.
8. Enter the relevant information and click the **Grant** button.
9. The system displays the message "Transaction Successfully Added...Click Ok to Continue". Click the **Ok** button.

4.10. BA888 - User Dashboard

Back-office User Dashboard is provided to enable a quick view on the status of the various batch activities; file uploads and monitors the transaction volumes across channels. The Dashboard also provides alert about specific events like End of Periods, Tax processing, etc. which will take place in the current day's batch.

Modes Available

Not Applicable

To view User Dashboard

1. Type the fast path **BA888** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Handoff > User Dashboard**.
2. The system displays the **User Dashboard** screen.

User Dashboard

ORACLE DEMO BANK Local Currency: CNY Welcome TADITYA9999 Date posting on 21/04/2013 Previous Login Details

Themes | Change Password | Help | About | Logout

Fast Path: BA888 Go

SEARCH

Customer Id:
 First Name:
 Last Name:

ALL TRANSACTION

- > Global Definitions
- > Transaction Processing
 - > Open Vault Batch
 - > Open Teller Batch

User Dashboard*

File Upload Statistics

Description	Count of Files
Files Processed	10
Files In Queue	0
File Processing Failed	12
Total Files Uploaded	22

Batch Category Status

Category Name	Status	Percentage Complete
In Consistency Check	Pending	0
Automatic write off	Pending	0
Mark for write off	Pending	0
BOD File Handoff	Pending	0
Batch Sweep Outs	Pending	0
New Report Category	Pending	0
Handoff after EOD	Pending	0
MONTHLY STATEMENTS	Pending	0
Scheduled Extracts	Pending	0
Tax Year End Process	Pending	0

Transaction Volume

Channel	Count of Transactions
BRN	0
FCR	50
IS	1
GEPU	10
Total Transactions	61

Batch Run Statistics

Date: 21/03/2013

Category Name	Start Time	End Time	Execution Time
Beginning of Day	2013-05-03 12:06:28	2013-05-03 13:38:12	1 hour, 31 minutes, 44 seconds.
Cutoff	2013-05-07 15:38:30	2013-05-07 16:31:58	53 minutes, 27 seconds.
End of Day	2013-05-07 16:34:32	2013-05-07 16:53:23	18 minutes, 51 seconds.

Indicators

CASA Rate Change Scheduled Today - Batch Timing to be Impacted.
 Month End Today.
 End of Period Processing for CASA - Batch timings to be impacted.

HY TRANSACTION

HY TODO LIST

Card | Change Pin | Cheque | Cost Rate | FCY Change | Denomination | Instrument | Inventory | Pin Validation | Service Charge | Signature | Travellers Cheque

Field Description

Field Name	Description
------------	-------------

File Upload Statistics	
------------------------	--

Field Name	Description
Total Files Uploaded	[Display] This field displays the total number of the files that have been uploaded.
Files Processed	[Display] This field displays the total number of files that have been processed.
Files in Queue	[Display] This field displays the total number of files that are in queue for processing.
File Processing Failed	[Display] This field displays the total number of files for which processing has failed.
Batch Category Status	
Category Name	[Display] This field displays the name of the category in order of execution.
Status	[Display] This field displays the status of the category for the current posting date. The values are: <ul style="list-style-type: none"> • Completed • Pending • Running • Aborted
Percentage Complete	[Display] This field displays the percentage completed. For completed status the value will be 100% For Running/Abort the actual value will be displayed. For Pending status, the value should be 0%
Transaction Volume	
Channel	[Display] This field displays the channel name.

Field Name	Description
Volume	<p>[Display]</p> <p>This field displays the transaction done through particular channel.</p>
Batch Run Statistics	
Category Name	<p>[Display]</p> <p>This field displays the name of the category.</p>
Start Time	<p>[Display]</p> <p>This field displays the start time for the category.</p>
End Time	<p>[Display]</p> <p>This field displays the time when the category was completed.</p>
Execution Time	<p>[Display]</p> <p>This field displays the total execution time inclusive time taken to resolve aborts if any .</p>
Indicators	<p>[Display]</p> <p>This field displays the indicators or alerts, as mentioned below.</p> <ul style="list-style-type: none"> • CASA Rate Change scheduled today - Batch timings to be impacted (This text should be displayed if there is a rate change schedule today) • Month-end today (This text should be displayed if the current date is a month-end) • End of Period Processing for CASA - Batch timings to be impacted (This text should be displayed if there is an End of Period processing for CASA scheduled today based on the product parameters) <p>Indicators should be blank, if any one of the conditions is not met.</p>

3. Click the Refresh button, to update the File Upload Statistics/Transaction Volume/Batch Category Status/Batch Run Statistics. This will update the record for any transaction done.
4. Click the **Close** button.

4.11. APM04 - Attribute Application Maintenance

This maintenance is used to apply attribute at a particular level i.e. at customer, sub-account, card, passbook or certificate in add mode.

In modify mode, expiry date of the attribute can be modified only if it is equal to greater than the current process date.

In delete mode, attributes placed at customer/ sub-account/ card/ passbook/ certificate can be deleted.

In inquiry mode, attributes placed at customer/ sub-account/ card/ passbook/ certificate can be inquired which are not expired.

Based on the value selected in the Attribute level, respective field will be enabled for inputting customer ID, sub-account no., card no., passbook or certificate no.

Definition Prerequisites

APM01 - Attributes Parameter Maintenance

Modes Available

Add, Modify, Delete, Inquiry.

To maintain Attribute Application

1. Type the fast path **APM04** and click **Go** or navigate through the menus to **Transaction Processing > Customer Transactions > Attribute Application Maintenance**.
2. The system displays the **Attribute Application Maintenance** screen.

Attribute Application Maintenance

Attributes Application Maintenance*

Attribute Level :

Customer ID : Customer Name :

Account No. : Account Title :

Card No. :

Passbook No. :

Certificate No. :

Stock Code : Stock Description :

MCA No. : MCA Title :

Attribute Name :

Expiry Date :

Remarks:

Record Details	Authorized By	Last Mnt. Date	Last Mnt. Action	Authorized
Input By				<input type="checkbox"/>

☐ Add
 ☐ Modify
 ☐ Delete
 ☐ Cancel
 ☐ Amend
 ☐ Authorize
 ☒ Inquiry

UDF OK Close Clear

Field Description

Column Name	Description
Attribute Level	<p>[Mandatory, Drop-Down]</p> <p>Select the Level at which a particular attribute is to be applied.</p> <p>The values given are:</p> <ul style="list-style-type: none"> Customer Sub-account Card Passbook Certificate
Customer ID	<p>[Optional, Numeric,10]</p> <p>Enter a valid customer ID.</p>
Customer Name	<p>[Display]</p> <p>This field displays the name of the customer.</p>

Column Name	Description
Sub account No.	[Numeric,16] Enter a valid CASA & TD sub account number.
Account Title	[Display] This field displays the account title of the account number entered.
Card No.	[Numeric,20] Enter a valid a valid Active Card Number
Passbook Number	[Numeric,20] Enter a valid a valid Active Passbook Number
Certificate Number	[Numeric,20] Enter a valid a valid Active Certificate Number
Stock Code	[Optional, Pick List] This field will be enabled only if Attribute Level is selected as Passbook and Certificate .
Stock Description	[Display] This filed displays the stock description for selected stock code
MCA Number	[Display] This field enables only if Sub-Account Number, Card Number, Passbook or Certificate Number is entered. In case of Card, default MCA linked to the card will be displayed.
MCA Title	[Display] This field will be displayed only if Sub-Account Number, Card Number, Passbook, Certificate Number is entered.
Attribute Name	[Mandatory, Pick List] Select the name of the attribute.
Expiry Date	[Optional Pick List, DD/MM/YYYY] Select the expiry date of the attribute from the pick list or enter it in DDMYY format. If not entered then will considered as no expiry date is present. The date should be equal to or greater than current process date. Attribute expiry date cannot be set as holiday.

- Click the **OK** button.
- The details are added once the record is authorized.

5. Inquiries

Transaction inquiries display detailed information about a transaction performed by the user.

This section explains how the system allows the user to view information about branch operations. The user can view the status of the transactions performed by the teller, branch-wise transactions, the errors committed by the tellers, last few transactions performed by each teller, reversal of transactions, etc. through various inquiry screens.

5.1. 7012 - Account No Check Digit Inquiry

The account number of a customer could consist of the bank code (two digits), branch code (four digits), a running serial number (six digits) and a check digit (two digits). The order of these entities as well as the weightage for each position in the account number for calculation of the check digits depends on the setup done in an internal table of **Oracle FLEXCUBE**.

Using this option you can retrieve the actual account number when the teller queries on an account, without giving the check digit(s). When the teller enters the account number without the check digit(s), the system automatically populates the check digits.

Definition Prerequisites

Not Applicable

Modes Available

Not Applicable

To view the account number check digit

1. Type the fast path **7012** and click **Go** or navigate through the menus to **Transaction Processing > Account Transactions > CASA Account Transactions > Inquiries > Account No Check Digit Inquiry**.
2. The system displays the **Account No Check Digit Inquiry** screen.

Account No Check Digit Inquiry

Account No Check Digit Inquiry*

Module :

Account No :

Card Change Pin Cheque Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

Field Description

Field Name	Description
Module	<p>[Mandatory, Drop-Down]</p> <p>Select the appropriate FLEXCUBE Retail module from the drop-down list..</p> <p>The options are:</p> <ul style="list-style-type: none"> • LN: Loans • TD: Term Deposit • CH: CASA Account • CI: Customer Information
Account No	<p>[Mandatory, Numeric, 16]</p> <p>The account number of the customer, without the check digits. The system will display the check digits.</p>

3. Select the module from the drop-down list.
4. Type the account number and press the **<Tab>** key.

Account No Check Digit Inquiry

Account No Check Digit Inquiry*

Module :

Account No :

Card Change Pin Cheques Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

5. The system displays the check digits of the account number. Click the **Close** button.

5.2. 7017 - Batch Status Inquiry

Using this option you can view the status of all the batches pertaining to the tellers and the vault tellers according to the posting dates in that particular branch. The status displays whether a particular teller, vault batch or branch batch is opened or closed.

Apart from this, the inquiry also displays the open batch of the previous posting date. The batch can be opened simultaneously for maximum two posting dates.

This option is used by the supervisor/manager of the branch to find out the overall status of all batches.

Definition Prerequisites

- 9001 - Open Teller Batch
- 9003 - Open Vault Batch

Modes Available

Not Applicable

To view the batch status

1. Type the fast path **7017** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Inquiries > Batch Status Inquiry**.
2. The system displays the **Batch Status Inquiry** screen.

Batch Status Inquiry

Batch Status Inquiry*

Field Description

Column Name	Description
Posting Date	<p>[Display]</p> <p>This column displays the posting date for which a batch has been opened or closed earlier.</p> <p>A batch can be opened for two consecutive dates. The system will not allow the user to open a batch for more than two consecutive days.</p>
User ID	<p>[Display]</p> <p>This column displays the ID of the user whose batch is opened or closed for the respective posting date.</p>
User Name	<p>[Display]</p> <p>This column displays the name of the user corresponding to the user ID whose batch is opened or closed for the respective posting date.</p>
Category	<p>[Display]</p> <p>This column displays the category of the user.</p> <p>The options are:</p> <ul style="list-style-type: none"> • Teller • Branch • Vault
Batch Status	<p>[Display]</p> <p>This column displays the status of the batch.</p> <p>The options are:</p> <ul style="list-style-type: none"> • Open • Closed

3. Click the **Cancel** button.

5.3. BAM95 - Branch Batch Status - Inquiry

Using this option, you are provided with the status of all the branch batches opened and closed branch-wise, for all posting dates with the date and the time of opening and closure . This inquiry displays the status of all the branch batches on the various process dates and does not display the status of the teller batch.

The data can be filtered branch-wise and status-wise. Inquiry can be performed for:

- All batches that are Open
- All batches that are Closed
- All batches that are Confirmed
- All Batches irrespective of their status

Definition Prerequisites

- 6001 - Batch Open

Modes Available

Not Applicable

To view the branch batch status

1. Type the fast path **BAM95** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Inquiries > Branch Batch Status-Inquiry**.
2. The system displays the **Branch Batch Status - Inquiry** screen.

Branch Batch Status - Inquiry

Branch Batch Status-Inquiry*

Branch Code:

Branch Status:

First

Previous

0

/0

Next

Last

Branch Code	Branch Name	Txn Date	Txn Time	Date Post	Batch Status

Card

Change Pin

Cheque

Cost Rate

Denomination

Instrument

Inventory

Pin Validation

Service Charge

Signature

Travellers Cheque

UDF

OK

Close

Clear

Field Description

Field Name	Description
Branch Code	<p>[Mandatory, Drop-Down]</p> <p>Select the code of the branch from the drop-down list.</p> <p>The list contains the short name of all the branches of the bank.</p>
Branch Status	<p>[Mandatory, Drop-Down]</p> <p>Select the status of the branch from the drop-down list.</p> <p>This will filter the inquiry result on the basis of the selected branch status.</p> <p>The options are:</p> <ul style="list-style-type: none"> • All • Batch Open • Batch Close • Batch Confirm

Column Name	Description
Branch Code	[Display] This column displays the code of the branch selected in the Branch Code field.
Branch Name	[Display] This column displays the name of the selected branch.
Txn Date	[Display] This column displays the date on which the transaction was performed.
Txn Time	[Display] This column displays the system time when the transaction was posted in the branch.
Date Post	[Display] This column displays the posting date for which the branch batch was opened, closed or confirmed.
Batch Status	[Display] This column displays the batch status. The options are: <ul style="list-style-type: none"> • All • Batch Open • Batch Close • Batch Confirm If the inquiry has been filtered on the basis of the batch status, this column displays the value selected in the Batch Status field. For example, if you select the Batch Open option in the Batch Status field, this column displays the batches with an open status.

3. Select the branch code and the branch status from the drop-down list.
4. The system displays the branch batch status.

Branch Batch Status - Inquiry

Branch Batch Status-Inquiry*

Branch Code: Branch Status:

First Previous of 1 2 Next Last

Branch Code	Branch Name	Trn Date	Trn Time	Date Post	Batch Status
9999	Centras	10/12/2008	15:25:21	31/01/2008	BATCH OPEN
9999	Centras	10/12/2008	15:24:53	15/01/2008	BATCH FORCE CLOSE
9999	Centras	05/12/2008	09:53:07	15/01/2008	BATCH OPEN
9999	Centras	28/11/2008	10:13:43	31/12/2007	BATCH OPEN
9999	Centras	10/12/2008	15:04:38	31/12/2007	BATCH FORCE CLOSE
9999	Centras	05/12/2008	09:51:59	15/12/2007	BATCH FORCE CLOSE
9999	Centras	22/11/2008	15:01:04	15/12/2007	BATCH OPEN
9999	Centras	06/11/2008	19:43:34	30/11/2007	BATCH OPEN
9999	Centras	28/11/2008	10:11:25	30/11/2007	BATCH FORCE CLOSE
9999	Centras	07/11/2008	19:03:15	15/11/2007	BATCH CONFIRM

Card Change Pin Cheque Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

- Click the **Close** button.

5.4. 7041 - Branch Totals Position

Using this option, the total amount and the number of debit and credit cash transactions for a particular branch can be viewed. Details of transfer transactions for a given currency and for the current posting date are also displayed.

There is a separate position for the vault teller of the branch and a common position for the total of all the other tellers of the branch.

Definition Prerequisites

- 9001 - Open Teller Batch
- 9003 - Open Vault Batch

Modes Available

Not Applicable

To view branch totals position

1. Type the fast path **7041** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Inquiries > Branch Totals Position**.
2. The system displays the **Branch Totals Position** screen.

Branch Totals Position

Branch Totals Position*

Currency : Posting Date : 31/01/2008

Transactions	Type	Opening Balance	Debits	Count	Credits	Count	Closing Balance
Vault	Cash :	<input type="text" value="0.00"/>	<input type="text" value="0.00"/>	<input type="text" value="0"/>	<input type="text" value="0.00"/>	<input type="text" value="0"/>	<input type="text" value="0.00"/>
Teller	Cash :	<input type="text" value="0.00"/>	<input type="text" value="0.00"/>	<input type="text" value="0"/>	<input type="text" value="0.00"/>	<input type="text" value="0"/>	<input type="text" value="0.00"/>

Transfer Amount :

Transfer Count :

Card Change Pin Cheque Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

Field Description

Field Name	Description
Currency	<p>[Mandatory, Drop-Down]</p> <p>Select the currency to view the transactions done in that currency from the drop-down list.</p> <p>For example, if you select USD, the system will display the transaction done in USD.</p>
Posting Date	<p>[Mandatory, dd/mm/yyyy]</p> <p>Type the posting date.</p> <p>By default, the system displays the current posting date.</p> <p>The date should be the one of the dates for which the batches are open.</p>
Transactions Type	<p>[Display]</p> <p>This field displays the type of transaction carried out by the teller in the selected currency.</p>
Opening Balance	
Vault	<p>[Display]</p> <p>This field displays the opening balance amount of the branch vault in the selected currency.</p>
Teller	<p>[Display]</p> <p>This field displays the opening balance amount of all the branch tellers, for the cash transaction in the selected currency.</p>
Debits	
Vault	<p>[Display]</p> <p>This field displays the total cash debit in a branch vault for a particular posting date in the selected currency.</p>
Teller	<p>[Display]</p> <p>This field displays the total debit in cash transactions performed by all the branch tellers for a particular posting date in the selected currency.</p>
Count	
Vault	<p>[Display]</p> <p>This field displays the total count of cash debits in the vault of a branch for a particular posting date in the selected currency.</p>
Teller	<p>[Display]</p> <p>This field displays the total count of the debit cash transactions performed by all branch tellers for a particular posting date in the selected currency.</p>

Field Name	Description
Credits	
Vault	<p>[Display]</p> <p>This field displays the total cash credit in a branch vault for a particular posting date in the selected currency.</p>
Teller	<p>[Display]</p> <p>This field displays the total credit in cash transactions performed by all the tellers of a branch for a particular posting date in the selected currency.</p>
Count	
Vault	<p>[Display]</p> <p>This field displays the total count of cash credit in a branch vault for a particular posting date in the selected currency.</p>
Teller	<p>[Display]</p> <p>This field displays the total count of the credit cash transactions performed by all branch tellers for a particular posting date in the selected currency.</p>
Closing Balance	
Vault	<p>[Display]</p> <p>This field displays the closing balance amount of the branch vault in the selected currency.</p> <p><i>Closing Balance = (Opening Balance + Credit balance) – Debit balance</i></p>
Teller	<p>[Display]</p> <p>This field displays the closing balance amount of all branch tellers, for the cash transaction in the selected currency.</p> <p><i>Closing Balance = (Opening Balance + Credit balance) – Debit Balance</i></p> <p>For example, if the opening balances of all branch tellers is 100,000 and there was a credit transaction of 50,000 and a debit transaction of 25,000.</p> <p>Thus, the closing balance will be as follows:</p> <p><i>Closing Balance = (1,00,000 + 50,000) – 25,000</i></p> <p>Therefore, the closing balance will be 125,000.</p>
Transfer Amount	<p>[Display]</p> <p>This field displays the amount of the funds transferred by the teller for a particular posting date in the selected currency.</p>

Field Name	Description
Transfer Count	[Display] This field displays the count of the funds transferred by the teller for a particular posting date in the selected currency.

3. Select the currency from the drop-down list.
4. Enter the posting date and click the **Ok** button.
5. The system displays the branch totals position details.

Branch Totals Position

Branch Totals Position*

Currency : INR Posting Date : 15/02/2008

Transactions	Type	Opening Balance	Debits	Count	Credits	Count	Closing Balance
Vault	Cash :	5,790,000.00	0.00	0	0.00	0	5,790,000.00
Teller	Cash :	244,010,678,655.31	45,000.00	5	2,263,954.00	14	244,012,697,609.31

Transfer Amount : 0.00

Transfer Count : 0

OK Close Clear

6. Click the **Close** button.

5.5. 7122 - Cross Rate Enquiry

Using this option you can search and view the exchange rate between two different currencies, against the bank's local currency. This option also displays the cross rate between two currencies. Cross rate is helpful when three currencies are involved.

For instance, many countries recognize the major currencies, viz. US Dollar, EURO, Yen and Great Britain Pound for export or import billing.

For example, an Arab Emirates company raises the bill in AED currency for exporting goods to India. At the time of payment, the Indian bank will calculate the equivalent cross rate from AED currency to USD currency. The amount derived in US Dollar will be converted to Indian Rupees, and that amount in Indian Rupees will be debited to the importer's account.

Definition Prerequisites

- BAM25 - Currency Definition
- Exchange rates of all currencies with respect to the local currency for the respective posting date should be defined.

Modes Available

Not Applicable

To view the cross rate

1. Type the fast path **7122** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Inquiries > Cross Rate Enquiry**.
2. The system displays the **Cost Rate Enquiry** screen.

Cost Rate Enquiry

Cross Rate Enquiry+

Source Currency : Target Currency :

Source Ccy Rate : Dest Ccy Rate :

Cross Rate :

Card | Change Pin | Cheque | Cost Rate | Denomination | Instrument | Inventory | Pin Validation | Service Charge | Signature | Travellers Cheque

LDF OK Close Clear

Field Description

Field Name	Description
Source Currency	[Mandatory, Drop-Down] Select the currency, which is to be converted from the drop-down list.
Target Currency	[Mandatory, Drop-Down] Select the currency against which the exchange rates need to be obtained from the drop-down list.
Source Ccy Rate	[Display] This field displays the source currency exchange or conversion rate against the local currency of the bank.
Dest Ccy Rate	[Display] This field displays the target currency exchange or conversion rate against the local currency of the bank.

Field Name	Description
Cross Rate	[Display] This field displays the rate of conversion of the source currency against the conversion rate of the target currency in terms of the bank's local currency.

3. Select the source currency and the target currency from the drop-down list.
4. Click the **Ok** button.
5. The system displays the cross rate details.

Cost Rate Enquiry

The screenshot shows a window titled "Cross Rate Enquiry*". It contains the following fields:

- Source Currency :
- Target Currency :
- Source Coy Rate :
- Dest Coy Rate :
- Cross Rate :

At the bottom of the window, there is a navigation bar with the following tabs: Card, Change Pin, Cheque, Cost Rate, Denomination, Instrument, Inventory, Pin Validation, Service Charge, Signature, and Travellers Cheque. Below these tabs are four buttons: UDF, OK, Close, and Clear.

6. Click the **Close** button.

5.6. 7008 - Last Ten Transactions

Using the option a teller can view the details of the last ten monetary transactions performed on the posting date. You can enquire the transactions for the current or for next posting date.

The system provides details on transaction type, date of transaction with time, account number, currency of the transaction, transaction amount and Dr/Cr indicator.

Definition Prerequisites

- 9001 - Open Teller Batch

Modes Available

Not Applicable

To view the last ten transactions

1. Type the fast path **7008** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Inquiries > Last Ten Transactions**.
2. The system displays the **Last Ten Transactions** screen.

Last Ten Transactions

The screenshot shows the 'Last Ten Transactions' window. At the top, there's a header bar with 'User No : TKATDARE' and 'Date : 31/01/2008'. Below the header is a table with the following columns: Seq No, Type, Txn Date, Txn Time, Acct No, Ccy, Txn Amt, and Dr / Cr. The table is currently empty. At the bottom of the window, there is a navigation bar with buttons for Card, Change Pin, Cheque, Cost Rate, Denomination, Instrument, Inventory, Pin Validation, Service Charge, Signature, and Travellers Cheque. Below the navigation bar, there are four buttons: UDF, OK, Close, and Clear.

Field Description

Field Name	Description
User No	[Display] This field displays the user ID of the teller who has logged in. Only those transactions performed by the teller who has logged in are displayed.
Date	[Mandatory, Numeric, dd/mm/yyyy] Type the posting date of the transaction. By default, the system displays the current posting date.

Column Name	Description
Seq No	[Display] This column displays the sequence number pertaining to the transaction carried out by the teller.
Type	[Display] This column displays the type of transaction performed by the teller.
Txn Date	[Display] This column displays the date on which the teller performed the transaction.
TxnTime	[Display] This column displays the system time when the teller performed the transaction.
Acct No	[Display] This column displays the account numbers for which the teller has performed the transactions.
Ccy	[Display] This column displays the code of the currency in which the teller performed the transaction.
Txn Amt	[Display] This column displays the amount for which the transaction was performed in the transaction currency.

Column Name	Description
Dr / Cr	<p>[Display]</p> <p>This column displays whether the transaction performed was a debit transaction or a credit transaction.</p> <p>The options are:</p> <ul style="list-style-type: none"> • D: Debit transactions • C: Credit transactions

- Enter the posting date of the transaction.
- Click the **OK** button.
- The system displays the details of the last ten transactions.

Last Ten Transactions

The screenshot shows a window titled "Last Ten Transactions*" with a yellow header bar. Below the header, there are input fields for "User No" (TKATDARE) and "Date" (31/01/2008). A table displays transaction details with the following columns: Seq No, Type, Txn Date, Txn Time, Acct No, Ccy, Txn Amt, and Dr / Cr. The table contains one row with the following data: Seq No 17, Type FTD, Txn Date 12/12/2008, Txn Time 16:08:55, Acct No 60000000714840, Ccy CAD, Txn Amt 996.58, and Dr / Cr D. Below the table, there is a navigation bar with buttons for Card, Change Pin, Cheque, Cost Rate, Denomination, Instrument, Inventory, Pin Validation, Service Charge, Signature, and Travellers Cheque. At the bottom right, there are buttons for LDF, OK, Close, and Clear.

Seq No	Type	Txn Date	Txn Time	Acct No	Ccy	Txn Amt	Dr / Cr
17	FTD	12/12/2008	16:08:55	60000000714840	CAD	996.58	D

- Click the **Close** button.

5.7. 7050 - Old To New Account Inquiry

When the bank has migrated from a different system to **Oracle FLEXCUBE** or from an old **Oracle FLEXCUBE** release to a new **Oracle FLEXCUBE** release, the account number of all customer accounts might need to be changed.

Using this option you can support the transition period wherein customers quote the old account numbers at the branch to perform transactions. It determines the new account number on which the transaction(s) are to be performed. The system also provides the customer name for proper verification of old to new account.

Definition Prerequisites

Not Applicable

Modes Available

Not Applicable

To view the new account number

1. Type the fast path **7050** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Inquiries > Old To New Account Inquiry**.
2. The system displays the **Old To New Account Inquiry** screen.

Old To New Account Inquiry

Old To New Account Inquiry*

Old Account Number :

Old Deposit Number :

Flexcube Acct No :

Flexcube Dep No :

Customer Name :

Card Change Pin Cheque Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

Field Description

Field Name	Description
Old Account Number	[Mandatory, Alphanumeric, 16] Type the old account number of the customer which has to be changed.
Old Deposit Number	[Mandatory, Alphanumeric, 16] Type the old deposit number of the customer.
Flexcube Acct No	[Display] This field displays the details of the FLEXCUBE Retail account number after entering the old account number.
Flexcube Dep No	[Display] This field displays the details of the FLEXCUBE Retail deposit number.
Customer Name	[Display] This field displays the name of the customer who holds the account.

3. Enter the old account number and deposit number.
4. Click the **Ok** button.
5. The system displays the new account number.

Old To New Account Inquiry

Old To New Account Inquiry*

Old Account Number :

Old Deposit Number :

Flexcube Acct No :

Flexcube Dep No :

Customer Name :

Card	Change Pin	Cheque	Cost Rate	Denomination	Instrument	Inventory	Pin Validation	Service Charge	Signature	Travellers Cheque
------	------------	--------	-----------	--------------	------------	-----------	----------------	----------------	-----------	-------------------

6. Click the **Close** button.

5.8. 6006 - Search Electronic Journal

The tellers and the supervisors can view the status of all the transactions performed by them during the posting date for which the teller batch is opened. The teller can view the status of only those transactions done by them. However, the supervisor can view the status of all the transactions done by all the tellers.

Using this option, the teller can also reverse the transaction posted by him during the day. This option can be used to view the list of all transactions. The incomplete transactions are those transactions that have been initiated by the teller and require authorization for completion.

After performing a transaction which needs authorization, the system prompts the teller to send the transaction for remote authorization or for local authorization. If the user selects remote authorization, the system prompts the user to select a supervisor. After the teller selects the supervisor, and confirms sending the transaction for authorization, the supervisor can view the transaction on their terminal by using this option. The Teller ID drop-down list in this option displays a list of tellers and the vault tellers who have sent the transactions for authorization to that supervisor.

Whenever any transaction is sent for remote authorization, the transaction sequence number is displayed at the teller / vault teller level. After the authorization of a transaction, the screen remains unchanged, so that the supervisor can select the next transaction for authorization.

This screen allows **Partial Reversal** for transactions that take place through

- a. **Cash Deposit (Fast Path - 1401)**
- b. **Cash Withdrawal (Fast Path - 1001 and Fast Path - 1013)**

It also allows **Same Day/ Any Day Partial Reversal** for following transactions -

- a. **CASA fund transfer (Fast Path - 1006)**
- b. **GL fund transfer (Fast Path - 1005 and Fast Path - 1008)**

Same day reversal is allowed for PPF transactions performed. The PPF which is done in the last needs to be reversed first and so on.

Definition Prerequisites

- Existence of Transactions for authorization / reversal

Modes Available

Not Applicable

To view and authorize the records sent for remote authorization

1. Type the fast path **6006** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Inquiries > Search Electronic Journal**.
2. The system displays the **Search Electronic Journal** screen.

Search Electronic Journal

Search Electronic Journal*

Teller ID :

☒ Electronic Journal ☐ Remote Authorization

Branch Posting Date : Host Process Date :

Account No :

From Sequence No : To Sequence No :

From Txn Time : To Txn Time :

From Amount : To Amount :

Mnemonic :

Incomplete Transactions : ☐ Remote Authorized Transactions : ☐

Seq No	Txn Code	Txn Time	Account No	Ccy	State	Amount	User ID	Print Receipt

0/0

Card Change Pin Cheque Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF Fetch Close Clear

Field Description

Field Name	Description
------------	-------------

Teller ID

[Conditional, Pick list]

Select the teller Id from the pick list. The pick list contains teller IDs from all the branches.

By default, the system displays the **All** option.

This field is enabled in the **Supervisor** login.

You can select either **Electronic Journal** or **Remote Authorization**.

Electronic Journal

[Optional, Radio Button]

Select **Electronic Journal** to view or reverse the transactions executed during the day.

Remote Authorization

[Optional, Radio Button]

Select **Remote Authorization** to authorize the transactions posted by tellers for authorization.

The following fields are enabled if **Electronic Journal** is selected.

Field Name	Description
Branch Posting Date	<p>[Mandatory, dd/mm/yyyy]</p> <p>Type the branch posting date for which the inquiry is to be made.</p> <p>This date should be one of the dates for which the batches are open. The field accepts back dated postings as well.</p> <p>The system by default displays the current posting date.</p>
Host Process Date	<p>[Mandatory, dd/mm/yyyy]</p> <p>Type the host process date for which the inquiry is to be made.</p>
Account No	<p>[Optional, Numeric, 16]</p> <p>Type the account number.</p>
From Sequence No	<p>[Mandatory, Numeric, Four]</p> <p>Type the start number for the sequence range.</p>
To Seq No	<p>[Mandatory, Numeric, Four]</p> <p>Type the end number for the sequence range.</p>
From Txn Time	<p>[Mandatory, HH:MM:SS]</p> <p>Type the start time of the time range.</p>
To Txn Time	<p>[Mandatory, HH:MM:SS]</p> <p>Type the end time of the time range.</p>
From Amount	<p>[Mandatory, Numeric, 13, Two]</p> <p>Type the from amount.</p>
To Amount	<p>[Mandatory, Numeric, 13, Two]</p> <p>Type the to amount.</p>
Mnemonic	<p>[Optional, Pick List]</p> <p>Select the mnemonic code, to filter the transactions carried out by the teller, from the pick list.</p> <p>The pick list displays the mnemonic codes of all the transactions that are maintained in Oracle FLEXCUBE.</p>
Incomplete Transactions	<p>[Optional, Check Box]</p> <p>Select the check box to view the list of incomplete transactions.</p>
Remote Authorized Transactions	<p>[Optional, Check Box]</p> <p>Select the Remote Authorized Transactions check box to view the list of transactions which have been remotely authorized.</p>

Column Name	Description
Seq No	[Display] This column displays the sequence number of the transactions carried out by the teller.
Txn Code	[Display] This column displays the mnemonic code for the transactions carried out by the teller.
Txn Time	[Display] This column displays the system time when the transaction was posted in the branch.
Account No	[Display] This column displays the account number on which the transaction was carried out by the teller.
Ccy	[Display] This column displays the currency in which the transaction was done.
State	[Display] This column displays the status of the transaction.
Amount	[Display] This column displays the amount in the transaction currency.
User ID	[Display] This column displays the unique identification of the teller who has committed the transaction.
Print Receipt	[Link] Click the Click to Print link to print the document receipt. For more information on Document Receipt screen, refer to the Common Screens option available in the Oracle FLEXCUBE Introduction User Manual .

3. Select **Electronic Journal** option and click the **Fetch** button to reverse a transaction, if required.

Search Electronic Journal

Search Electronic Journal*

Teller ID :

☒ Electronic Journal ☐ Remote Authorization

Branch Posting Date : Host Process Date :

Account No :

From Sequence No : To Sequence No :

From Txn Time : To Txn Time :

From Amount : To Amount :

Mnemonic :

Incomplete Transactions : ☐ Remote Authorized Transactions : ☐

Seq No	Txn Code	Txn Time	Account No	Ccy	State	Amount	User ID	Print Receipt
6	1401	18:47:01	06049420000012	INR	Incomplete	1,000.00	TSRINIVASA	Click to print
5	1401	17:52:46	06049420000012	INR	Sent	1,000.00	TSRINIVASA	Click to print
4	1401	17:51:10	06049410000019		Cancelled	0.00	TSRINIVASA	Click to print
3	8051	18:39:45	06056900000019		Sent	0.00	TSRINIVASA	Click to print
2	8053	12:24:50			Sent	0.00	TSRINIVASA	Click to print
1	9001	17:53:26			Success	0.00	TSRINIVASA	Click to print

1 / 1

Card Change Pin Cheque Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF: Fetch Close Clear

- Double-click the sequence number in the **Seq No** column.
- The system displays the relevant screen through which the transaction was performed.

Cash Deposit - Correction Reverse

Cash Deposit

Account No. : 1000800000000166 STANDARD MOBILES

Account Ccy. : RMB Txn Ccy. : RMB

Account Ccy. Rate : 1.00000 Txn Ccy. Rate : 1.00000

Txn Amount : 3,251.00

Account Amount : 3,251.00

Value Date : 27/12/2011

User Reference No. : A

Narrative : Cash Deposit

Card	Change Pin	Cheque	Cost Rate	Handle FCY Charge	Denomination	Instrument	Inventory	Pin Validation	Service Charge	Signature	Travellers Cheque
Previous	Next	Reverse	Correction Reverse	View	Back	UDF	Fetch	Close	Clear		

6. Click the **Reverse** button to reverse the transaction. The system displays the message "Transaction Completed Successfully".
7. Click the **Correction Reverse** button for same day reversal. This button is enabled only for same day reversal (i.e. when branch posting date field in **Search Electronic Journal (Fast Path- 6006)** screen is same as that of current system date).
8. Click the **Partial Reverse** button to pass the accounting entry with negative amount inputted in transaction amount field. This button is enabled only for partial reversal of transactions. (Partial button is enabled only when the Amount Field is modified)
9. **Correction reverse** and **Reverse** button are invisible for partial reversal, as shown below --

Partial Reverse

Cash Deposit

Account No. :
Account Ccy. :
Account Ccy. Rate :
Txn Amount :
Account Amount :
Value Date :
User Reference No. :
Narrative :

1000800000000166
RMB
1.00000
3,200.00
3,200.00
27/12/2011
A
Cash Deposit

STANDARD MOBILES
Txn Ccy. :
Txn Ccy. Rate :
RMB
1.00000

CardChange PinChequeCost RateHandle FCY ChargeDenominationInstrumentInventoryPin ValidationService ChargeSignatureTravellers Cheque

PreviousNextPartial ReverseViewBackUDFFetchCloseClear

To view and authorize the records sent for remote authorization

1. Select **Remote Authorization** option and click the **Fetch** button.

Remote Authorization

Search Electronic Journal

Teller ID :

☐ Electronic Journal ☒ Remote Authorization

Branch Posting Date :

Account No :

From Sequence No :

From Txn Time :

From Amount :

Mnemonic :

Incomplete Transactions : ☐

Host Process Date :

To Sequence No :

To Txn Time :

To Amount :

Remote Authorized Transactions : ☐

Seq No	Txn Code	Amount	User ID	Description
3	1356	10,000.00	TDEVLOAN2	2502
1	1356	10,000.00	SDEVTD3	2521
15	1006	56.00	TDEVIDEA1	2563
2001	CH050	0.00	TDEVGL1	387
2002	CH050	0.00	TDEVGL1	387
5001	7115	0.00	TDEVCSA2	2505
5003	7115	0.00	TDEVCSA2	2505

1 / 1

2. Double-click the sequence number in the **Seq No** column.
3. The system displays the relevant screen.

Cash Deposit

Account No. : 06049410000019 EDWARD MATHEW

Account Ccy. : INR Txn Ccy. : INR

Account Ccy. Rate : 1.00000 Txn Ccy. Rate : 1.00000

Txn Amount : 1,000.00

Account Amount : 1,000.00

Value Date : 15/01/2008

User Reference No. :

Narrative : Cash Deposit

Card Change Pin Cheque Cost Rate Denomination Instrument **Inventory** Pin Validation Service Charge Signature Travellers Cheque

Grant Deny View Back UIDF Fetch Close Clear

4. Click the **Grant** button to authorize the transaction. The system displays the dialog box for confirming amount.
5. Enter the amount and click **Ok** button. The system displays the authorization screen.
6. Enter the relevant information.
7. Click **Grant** button for record authorization.

5.9. 7040 - Teller Totals Position

Using this option a teller can view his/her own position and the total transactions performed by any teller for a particular currency on the posting date.

A supervisor can view the position of any teller in his/her branch. This inquiry is only for teller cash and funds transfer position. Cash and transfer transaction details are grouped separately. The total transaction count and amount are provided. You can enquire the transactions for the current or for next posting date. Cash and transfer transaction details are grouped separately. The total transaction count and amount are provided by the system.

Definition Prerequisites

- 9001 - Open Teller Batch

Modes Available

Not Applicable

To view the teller position and the total transactions performed by the teller

1. Type the fast path **7040** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Inquiries > Teller Totals Position**.
2. The system displays the **Teller Totals Position** screen.

Teller Totals Position

Teller Totals Position*

Teller Id : TKATDARE Currency : [dropdown] Posting Date : 31/01/2008 [calendar icon]

Txn Type : Opening Balance

Debits	Count	Credits	Count	Closing Balance
0.00	0	0.00	0	0.00

Cash : 0.00

Transfer Amount : 0.00

Transfer Count : 0

Card Change Pin Cheque Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

LDF OK Close Clear

Field Description

Field Name	Description
Teller Id	<p>[Display]</p> <p>This field displays the user ID of the teller who has logged in.</p> <p>In case of a supervisor login, the supervisor can view transaction details of all the tellers under his/her supervision.</p> <p>This field is editable in case of a supervisor login.</p>
Currency	<p>[Mandatory, Drop-Down]</p> <p>Select the currency, to view the total of all the transaction amounts with that currency from the drop-down list.</p> <p>For example, if you select USD, the system will display the total of all the transaction amounts, for transactions that have USD as their transaction currency.</p>
Posting Date	<p>[Mandatory, Numeric, dd/mm/yyyy]</p> <p>Type the posting date.</p> <p>By default, the system displays the current date.</p>
Txn Type	
Cash	
Opening Balance	<p>[Display]</p> <p>This field displays the opening balance amount of the teller for the cash transaction in the selected currency.</p>
Debits	<p>[Display]</p> <p>This field displays the total debit in cash transactions performed by a teller for a particular posting date in the selected currency.</p>
Count	<p>[Display]</p> <p>This field displays the total count of the debit cash transactions performed by a teller for a particular posting date in the selected currency.</p>
Credits	<p>[Display]</p> <p>This field displays the total credit amount of cash transactions performed by a teller for a particular posting date in the selected currency.</p>
Count	<p>[Display]</p> <p>This field displays the total count of the credit cash transactions performed by a teller for a particular posting date in the selected currency.</p>

Field Name	Description
Closing Balance	<p>[Display]</p> <p>This field displays the closing balance amount of the teller for the cash transaction in the selected currency.</p> <p><i>Closing Balance = (Opening Balance + Credit balance) – Debit balance</i></p> <p>For example, if the opening balance of a teller is 1,00,000 and the teller had a credit transaction of 50,000 and a debit transaction of 25,000.</p> <p>Then, the closing balance will be as follows:</p> <p>Closing Balance = (1,00,000 + 50,000) – 25,000</p> <p>Therefore, the closing balance will be 125,000.</p>
Transfer Amount	<p>[Display]</p> <p>This field displays the amount of the funds transferred by the teller for a particular posting date in the selected currency.</p> <p>This field displays the funds transferred from one CASA Account to another.</p>
Transfer Count	<p>[Display]</p> <p>This field displays the count of the funds transferred by the teller for a particular posting date in the selected currency.</p> <p>This field displays the count of funds transferred from one CASA Account to another.</p>

3. Select the currency from the drop-down list.
4. Click the **OK** button.
5. The system displays the teller totals position details.

Teller Totals Position

Teller Totals Position*

Teller Id : Currency : Posting Date :

Txn Type	Opening Balance	Debits	Count	Credits	Count	Closing Balance
Cash	<input type="text" value="0.00"/>	<input type="text" value="0.00"/>	<input type="text" value="0"/>	<input type="text" value="0.00"/>	<input type="text" value="0"/>	<input type="text" value="0.00"/>
Transfer Amount :	<input type="text" value="996.58"/>					
Transfer Count :	<input type="text" value="1"/>					

Card Change Pin Cheque Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

- Click the **Close** button.

5.10. 7015 - Teller Transactions Summary

Using this option the summary of all transactions performed by the teller on the current posting date for a specified currency can be viewed. A teller can view his/her own position.

A supervisor can view the position of any teller in his/her branch. You can enquire the transactions for the current or for next posting date. The system provides information on transaction type, description, number of transactions, total amount and service charge.

Definition Prerequisites

- BAM15 - Transaction Mnemonic Codes
- BAM25 - Currency Definition
- 9001 - Open Teller Batch

Modes Available

Not Applicable

To view the teller transactions summary

1. Type the fast path **7015** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Inquiries > Teller Transactions Summary**.
2. The system displays the **Teller Transactions Summary** screen.

Teller Transactions Summary

Teller Transactions Summary*

User No : TKATDARE Currency : Date : 31/01/2008

Description	Type	No Txns	Total Amount	Service Charge

0 /0

UDF OK Close Clear

Card Change Pin Cheque Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

Field Description

Field Name	Description
User No	[Display] This field displays the user ID of the teller who has logged in. Only those transactions performed by the teller who has logged in are displayed.
Currency	[Mandatory, Drop-Down] Select the currency to view the total of all the transaction amounts with that currency from the drop-down list. For example, if you select USD, the system will display the total of all the transaction amounts, for transactions that have USD as their transaction currency.
Date	[Mandatory, dd/mm/yyyy] Type the posting date. By default, the system displays the current posting date.

Column Name	Description
Description	[Display] This column displays the description of the transactions carried out by the teller. The description is maintained in the Transaction Mnemonic Codes (Fast Path: BAM15) option.
Type	[Display] This column displays the type of transaction carried out by the teller.
No Txns	[Display] This column displays the number of transactions of a particular type carried out by the teller for a particular posting date.
Total Amount	[Display] This column displays the total amount for a particular type of transaction, carried out by the teller for a particular posting date.
Service Charge	[Display] This column displays the total service charge amount for a particular type of transaction, carried out by the teller for a particular posting date.

3. Select the currency from the drop-down list.
4. Enter the posting date and click the **OK** button.
5. The system displays the teller transaction summary.

Teller Transactions Summary

Teller Transactions Summary*

User No : TKATDARE

Currency : CAD

Date : 31/01/2008

Description	Type	No Txns	Total Amount	Service Charge
FUNDS TRANSFER DEBIT	FTD	1	996.58	0.00

1

/1

1

Card

Change Pin

Cheques

Cost Rate

Denomination

Instrument

Inventory

Pin Validation

Service Charge

Signature

Travellers Cheque

UDF

OK

Close

Clear

6. Click the **Close** button.

5.11. 6010 - View Teller Errors

Using this option errors committed by the branch tellers can be viewed . The screen displays the overage or shortage booked by the teller on any day.

This is a report on the differences a teller has encountered between the actual cash present with the teller and the cash calculated by the system. A supervisor can view the teller errors for all tellers.

Definition Prerequisites

- The teller branch should be open for the current posting date.

Modes Available

Not Applicable

To view the teller errors

1. Type the fast path **6010** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Inquiries > View Teller Errors**.
2. The system displays the **View Teller Errors** screen.

View Teller Errors

View Teller Errors*

Teller Id : SDOC5

From Date : 29/02/2008 To : 29/02/2008

Currency :

Error Amount : 0.00 To : 999,999,999.00

Error Types are as follows :

1 = OVERAGE 2 = SHORTAGE

OK Close Clear

Field Description

Field Name	Description
Teller Id	<p>[Mandatory, Drop-Down]</p> <p>Select the user identification of the teller from the drop-down list.</p> <p>By default, this field displays the user ID of the teller who has logged in.</p> <p>The supervisor can view transaction details of all the tellers associated under his/her supervision.</p>
Date	<p>[Mandatory, dd/mm/yyyy]</p> <p>Type the appropriate date range to filter the transaction errors committed by the teller.</p> <p>The value in the To Date field should be greater than the From Date field.</p>
Currency	<p>[Mandatory, Drop-Down]</p> <p>Select the currency to view the total of all the transaction amounts with that currency from the drop-down list.</p> <p>For example, if you select USD, the system will display the total of all the transaction amounts, for transactions that have USD as their transaction currency.</p>
Error Amount	<p>[Mandatory, Numeric, 13, Two]</p> <p>Type the amount range to filter the transaction errors by amount, committed by the teller for a particular currency.</p> <p>The value in the End amount field should be greater than the Start amount field.</p> <p>By default, the system displays the amount range as 0.00 to 999,999,999.00.</p>

Column Name	Description
TxnDate	<p>[Display]</p> <p>This column displays the date on which the transaction has taken place.</p>
Type	<p>[Display]</p> <p>This column displays the type of transaction performed by the teller.</p>
Currency	<p>[Display]</p> <p>This column displays the currency in which the transaction has taken place.</p>
Amount	<p>[Display]</p> <p>This column displays the transaction amount.</p>

3. Select the appropriate teller id and currency from the drop-down list.
4. Select the from date and to date from the pick list.
5. Enter the error amount.
6. Click the **OK** button.
7. The system displays the teller error details.

View Teller Errors

View Teller Errors*

Teller Id :

From Date : To :

Currency :

Error Amount : To :

Error Types are as follows :

1 = OVERAGE 2 = SHORTAGE

Txn Date	Type	Currency	Amount
31/12/2007	1	INR	10.00

OK Close Clear

8. Click the **Close** button.

5.12. 6007-Transaction - Position Squaring Rate x-ref

In case of a cross-currency transaction the position squaring is done based on the rate already decided and maintained (presently Position squaring happens with the TC Rate maintained). While doing some high value cross-currency transactions the branch can negotiate with its higher office / head office and can arrive at a special negotiated position squaring rate so that additional profit can be booked in the branch. This screen helps to capture this negotiated position squaring rate for a transaction. The Search criteria in the screen are used to help the teller to identify the transaction, and then the rate can be added for that particular transaction. This position squaring rate input is not mandatory. If the teller does not input this rate, then the system should pick up the position squaring rate as per the present functionality.

Definition Prerequisites

- Not Applicable

Modes Available

- Not Applicable

To add billing details of loan accounts

1. Type the fast path **6007** and click **Go** or navigate through the menus to **Transaction Processing > Internal transaction> Inquiries**.
2. The system displays the **Transaction - Position Squaring Rate x-ref** screen.

Transaction - Position Squaring Rate x-ref

Transaction – Position Squaring Rate x-ref*

Teller ID : SDOC12

Posting Date : 21/09/2013

Account No :

From Sequence No : 1 To Sequence No : 99999999

From Txn Time : 00:00:00 To Txn Time : 23:59:59

From Amount : 0.00 To Amount : 9,999,999,999.99

Mnemonic : Transaction Reference No :

Seq No	Txn Code	Txn Time	Account No	Acct Ccy	Account Amount	User ID	Position Squaring Buying Rate	Position Squaring Selling Rate	Delete
<div>0/0</div> <div>Save</div>									

Card Change Pin Cheque Cost Rate FCY Change Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF Fetch Close Clear

Field Description

Field Name	Description
Teller ID	<p>[Mandatory, Pick list]</p> <p>Teller ID is one of the search criteria to filter the transactions.</p> <p>The field will be defaulted to the logged in Teller ID.</p> <p>The Pick List will display all the Teller and Supervisor ID. The user can select any other ID from the pick list.</p>
Posting Date	<p>[Display]</p> <p>Posting Date is one of the search criteria to filter the transactions.</p> <p>The Current process date is displayed by default and the date can be changed to previous date.</p> <p>For the current date transactions the position squaring rates can be added / modified / inquired.</p> <p>In case of previous date transactions the position squaring rates can only be inquired.</p>

Field Name	Description
Account No	[Optional, Numeric, 16] Account number is one of the search criteria to filter the transactions. Valid CASA / RD / TD / Loan account number.
From Sequence No	[Mandatory, Numeric, Four] For filtering the transactions, the Start sequence number to be inputted.
To Sequence No	[Mandatory, Numeric, Four] For filtering the transactions, the End sequence number to be inputted.
From Txn Time	[Mandatory, Numeric (HH:MM:SS), Eight] For filtering the transactions, the Start time to be inputted.
To Txn Time	[Mandatory, Numeric (HH:MM:SS), Eight] For filtering the transactions, the End time to be inputted.
From Amount	[Mandatory, Numeric , 15] For filtering the transactions, From Amount to be inputted.
To Amount	[Mandatory, Numeric , 15] For filtering the transactions, To Amount to be inputted.
Mnemonic	[Optional, Pick List] Transaction Mnemonic is one of the search criteria to filter the transactions.
Transaction Reference Number	[Optional, Alphanumeric , 40] Transaction Reference Number is one of the search criteria to filter the transactions.
Seq No	[Display] This field displays the sequence number of the transaction.
Txn Code	[Display] This field displays the mnemonic of the transaction.
Txn time	[Display] This field displays the Txn time of the transaction.
Account No	[Display] This field displays the Account No of the transaction.
Account Ccy	[Display] This field displays the Ccy of the account No of the transaction.

Field Name	Description
Account Amount	<p>[Display]</p> <p>This field displays the Amount of the transaction in account amount.</p>
User ID	<p>[Display]</p> <p>This field displays the User ID who has committed the transaction.</p>
Position Squaring Buying Rate	<p>[Display]</p> <p>The Position Squaring Buying Rate to be input/ displayed.</p> <p>This field will be enabled for input for FCY selling transactions only (example: USD cash withdrawal from RMB Account or any FCY - FCY transaction) For only FCY buying transaction this field will remain disabled for input (e.g. USD cash deposit in RMB account).</p> <p>If the Position Squaring Buying rate is already maintained for the transaction then the same will be displayed here and the same can be modified. .</p> <p>This field will be enabled for modification for current postings date transactions only. For previous posting date transactions this field will remain disabled.</p> <p>This screen will display only Cross-currency transactions as per the search criteria selected. Same currency transactions will not be displayed.</p>
Position Squaring Selling Rate	<p>[Display]</p> <p>The Position Squaring Selling Rate to be input/ displayed .</p> <p>This field will be enabled for input for FCY buying transaction only. (e.g. USD cash deposit in RMB Account or any FCY - FCY transaction) For only FCY selling transaction this field will remain disabled for input (e.g. USD cash withdrawal from RMB account).</p> <p>If the Position Squaring Selling rate is already maintained for the transaction then the same will be displayed here and the same can be modified.</p> <p>This field will be enabled for modification for current posting date transactions only. For previous posting date transactions this field will remain disabled.</p> <p>This screen will display only Cross-currency transactions as per the search criteria selected. Same currency transactions will not be displayed.</p>

Field Name	Description
Delete	<p>[Optional, Check Box]</p> <p>If the Position squaring rates already maintained are to be deleted then this checkbox to be checked.</p> <p>This check box will be enabled for the current posting date transactions only.</p> <p>For the earlier posting date transactions this check box will remain disabled.</p> <p>The functionality of this field is to delete the modification done in the Position Squaring Buy Rate or Position Squaring Sale Rate done by User. When this check box is checked and clicked on Save button, system will delete the modifications and will display the original rates used at the time of transaction.</p>

3. Click the **Fetch** button to fetch the records.
4. Once the Fetch button is clicked the system will display the cross-currency transactions as per the search criteria selected.
5. The teller can input the position squaring rates if required for the current dated transactions.
6. Click the **Save** button. The system will save new rates.
7. When **Delete** check box is checked and clicked on **Save** button, system will delete the modifications and will display the original rates used at the time of transaction.

6. Report Generation Transactions

Management, operational staff and customers need reports to acquire information or status of the transactions/activities performed on the system. Every bank branch is responsible for issuing an advice to their customers against every transaction performed in their respective accounts.

By default, all the reports, adhoc and batch, are generated in the central **FLEXCUBE Retail** application server.

This section deals with maintaining the report control, requesting for the reports and advices and generating or canceling the requested reports and advices.

6.1. BAM16 - Report Control Maintenance

Using this option the setup can control the generation of various reports by **Oracle FLEXCUBE**. Reports can be generated as adhoc reports or batch reports.

The adhoc reports are generated on demand or online using the **Report Request** (Fast Path: 7775) option from a branch terminal. The batch reports are automatically generated during the end of day or beginning of day operations. You can also maintain the module to which the report belongs to and the frequency of generation of reports in this option.

Definition Prerequisites

Not Applicable

Modes Available

Add, Modify, Delete, Cancel, Amend, Authorize, Inquire. For more information on the procedures of every mode, refer to **Standard Maintenance Procedures**.

To add the report control details

1. Type the fast path **BAM16** and click **Go** or navigate through the menus to **Global Definitions > Other > Report Control Maintenance**.
2. The system displays the **Report Control Maintenance** screen.

Report Control Maintenance

Report Control Maintenance

Report Id. :

Module :

Report/Advice :

Report Name :

Report Type :

Print Flag : ☐ Delete Flag : ☐ Total Copies :

Frequency : Priority :

Access Level : File Id. :

Invocation Var 1 :

Invocation Var 2 :

Invocation Var 3 :

Invocation Var 4 :

Invocation Var 5 :

Record Details

Input By : Authorized By : Last Mnt. Date : Last Mnt. Action : Authorized : ☐

☐ Add ☐ Modify ☐ Delete ☐ Cancel ☐ Amend ☐ Authorize ☒ Inquiry

Field Description

Field Name	Description
Report Id	<p>[Mandatory, Alphanumeric, 10]</p> <p>Type the report Id.</p> <p>The report ID is a unique number that is manually assigned. Once assigned, it helps to identify the report in FLEXCUBE Retail.</p>
Module	<p>[Mandatory, Drop-Down]</p> <p>Select the module to which the report belongs from the drop-down list.</p> <p>The options are:</p> <ul style="list-style-type: none"> • LN - Stands for Retail Loan • TD • CH - Stands for CASA • ST - Stands for Settlement • GL • COL - Stands for Online • CCI - Stands for Customer Information • CAP - Stands for Application Processing • CBS - Stands for Security based to users • CBA - Stands for Bank Global • CSM - Stands for Security Management • CTP - Stands for Transaction Processing • CTS - Stands for Tax Deduction at Source • CAT - Stands for ATM
Report/Advice	<p>[Mandatory, Drop-Down]</p> <p>Select the name of the advice/report for which the request has been maintained from the drop-down list.</p> <p>The options are:</p> <ul style="list-style-type: none"> • R - for a Report • A - for an Advice

Field Name	Description
Report Type	<p>[Mandatory, Drop-Down]</p> <p>Select the type of report from the drop-down list.</p> <p>The report type indicates the logical period in the FLEXCUBE Retail life cycle for generation of the report.</p> <p>The options are:</p> <ul style="list-style-type: none"> • EOD - The report is automatically printed during EOD • BOD -The report is automatically printed during BOD • Adhoc - The report will be available for adhoc printing • Branch - The report will be available in the branch for adhoc printing.
Report Name	<p>[Mandatory, Alphanumeric, 40]</p> <p>Type the name of the report.</p>
Print Flag	<p>[Optional, Check Box]</p> <p>Select the Print Flag check box to send the report automatically to the printer for printing.</p> <p>If the check box is cleared, the reports are spooled for future printing.</p>
Delete Flag	<p>[Optional, Check Box]</p> <p>Select the Delete Flag check box to delete the spooled report file after printing it.</p>
Total Copies	<p>[Mandatory, Numeric, Two]</p> <p>Type the number of copies of the report that are to be printed.</p>
Frequency	<p>[Mandatory, Drop-Down]</p> <p>Select the frequency at which the report is to be generated from the drop-down list.</p> <p>The options are:</p> <ul style="list-style-type: none"> • Daily • Weekly • Fortnightly • Monthly • Bimonthly • Quarterly • Half-yearly • Yearly

Field Name	Description
Priority	[Mandatory, Numeric, One] Type the priority level of the report. The reports will be printed according to their priority level.
Access Level	[Mandatory, Numeric, Two] Type the access level of the report. This is used to indicate the number of lines per page in the report. The level is usually any number between 0 and 60.
File Id.	This field is for future use.
Invocation Var 1 to 5	[Optional, Alphanumeric, 40] Type the parameters to be requested at the time of report generation. These parameters can customize the report generation.

3. Click the **Add** button.
4. Enter the report ID and press the **<Tab>** key.
5. Select the report type, module, report/advice and the frequency from the drop-down list.
6. Enter the name of the report and the invocation variance.

Report Control Maintenance

Report Control Maintenance

Report Id. :

Module :

Report/Advice :

Report Name :

Print Flag : ☒ Delete Flag : ☐

Frequency :

Access Level :

Invocation Var 1 :

Invocation Var 2 :

Invocation Var 3 :

Invocation Var 4 :

Invocation Var 5 :

Report Type :

Total Copies :

Priority :

File Id. :

Record Details

Input By	Authorized By	Last Mnt. Date	Last Mnt. Action	Authorized
<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="text"/>	<input type="checkbox"/>

☒ Add
 ☐ Modify
 ☐ Delete
 ☐ Cancel
 ☐ Amend
 ☐ Authorize
 ☐ Inquiry

7. Click the **Ok** button.
8. The system displays the message "Record Added...Authorization Pending...Click Ok to Continue". Click the **OK** button.
9. The report control details are added once the record is authorized.

6.2. 7775 - Report Request

Using this option reports and advices can be requested.

The request for two types of reports can be given, viz. adhoc reports and batch reports. The adhoc reports are generated on demand or on request, while the batch reports are automatically generated at the end of day or beginning of day.

The user can select the report type and the module to display the report categories. Each category has different reports, displayed along with their ID and title. The user can select the desired report from the list to generate it.

For more information, please refer to the respective module wise Reports Manual.

Definition Prerequisites

- BAM16 - Report Control Maintenance

Modes Available

Not Applicable

To request for a report

1. Type the fast path **7775** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Reports > Report Request**.
2. The system displays the **Report Request** screen.

Report Request

Report Request

☒ Adhoc Reports

☐ Batch Reports

Loans

Billing

Term Deposit

Customer Information

Security Management

Settlement

Origination

Relationship Pricing

Branch

Limit Management

Others

General Ledger

Savings

Safe Deposit Box

Report Group

Loans deviations Report

Loan EOD Reports

Loans Advices and Statements

Loans Interest and Arrears Report

Loans Daily Exception Reports

Loans Daily Transaction Reports

Loans NPA Report

Ok

Cancel

Field Description

Field Name	Description
Types of report	
Select the appropriate option to generate the report.	
The options are:	
<ul style="list-style-type: none">Adhoc ReportsBatch Reports	
By default, the Adhoc Reports option is selected.	
Adhoc Reports	[Mandatory, Radio Button] Click Adhoc Reports to generate and view an adhoc report.
Batch Reports	[Mandatory, Radio Button] Click Batch Reports to view EOD/BOD reports and advices for a particular batch.

Column Name	Description
Report Group	[Display] This column displays the different report groups under the different modules.

3. Select the appropriate option for the report type..
4. Click the appropriate tab for which you can generate/view reports. The system displays the report group lists.
5. Double-click the appropriate report group. The system displays the report title, and the corresponding report ID.
6. Double-click the report title. The system displays the **Input Parameters** screen. The number of input parameters will be determined by the nature of report, which is required.
7. Enter the relevant information and click the **Generate/View** button.

Note: Oracle Flexcube supports report generation in PDF, HTML and Excel formats. Based on the system configuration the reports can be generated in any of the above mentioned format.

6.3. 7780 - Advice/Report Cancel Request

Using this option, you can cancel advice/report request transactions that are sent for printing /viewing of generated ad-hoc advice /report.

In this option, only those requests placed by a particular user login ID can be cancelled.

Definition Prerequisites

- BAM16 - Report Control Maintenance
- 7775 - Report Request

Modes Available

Not Applicable

To perform the advice/report cancel request

1. Type the fast path **7780** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Reports > Advice/Report Cancel Request**.
2. The system displays the **Advice/Report Cancel Request** screen.

Advice/Report Cancel Request

Advice/Report Cancel Request*

Teller ID : TDOC3

ID	Report/Advice Name	R/A	Select
----	--------------------	-----	--------

0

Card Change Pin Cheque Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

Field Description

Field Name	Description
Teller ID	<p>[Display]</p> <p>This field displays the user ID of the teller who has logged in.</p> <p>Only those transactions performed by the teller who has logged in will be displayed.</p> <p>In case of a supervisor login, the supervisor can view all the report/advice requests of any teller associated under his/her supervision.</p> <p>This field is editable, in case of a supervisor login.</p>

Column Name	Description
ID	<p>[Display]</p> <p>This column displays the ID of the advice or report for which the request has been maintained.</p> <p>The report ID is added and maintained in the Report Control Maintenance (Fast Path: BAM16) option.</p>
Report/ Advice Name	<p>[Display]</p> <p>This column displays the name of the advice/report for which the request has been maintained.</p>
R / A	<p>[Display]</p> <p>This column displays whether the request has been maintained for an advice or a report.</p> <p>The options are:</p> <ul style="list-style-type: none"> • R: for a Report • A: for an Advice
Select	<p>[Optional, Check Box]</p> <p>Select the check box to cancel the corresponding advice/report.</p>

3. Select the appropriate check box in the **Select** column.

Advice/Report Cancel Request

Advice/Report Cancel Request*

Teller ID:

ID	Report/Advice Name	R/A	Select
AT001	Audit Trail Inquiry	A	<input checked="" type="checkbox"/>

/

Card | Change Pin | Cheque | Cost Rate | Denomination | Instrument | Inventory | Pin Validation | Service Charge | Signature | Travellers Cheque

4. Click the **OK** button.
5. The system will cancel the advice/report request. Click the **Close** button.

6.4. 7781 - Report Cancel All Tellers

Using this option, a supervisor can cancel advice/report request transactions sent by all users for printing /viewing of generated ad-hoc advice /report.

A supervisor can cancel advice/report requests in certain circumstances such as high load on network or if reports are not required urgently.

Definition Prerequisites

- BAM16 - Report Control Maintenance
- 7775 - Report Request

Modes Available

Not Applicable

To cancel the advice/report request for all the tellers

1. Type the fast path **7781** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Reports > Report Cancel All Tellers**.
2. The system displays the **Report Cancel All Tellers** screen.

Report Cancel All Tellers

Report Cancel All Tellers*

ID	Report/Advice Name	R/A	UserID	Select
CH334	Card Hold Details	R	TVINAY7	<input type="checkbox"/>
AT001	Audit Trail Inquiry	A	TBHAGWAT	<input type="checkbox"/>
AT001	Audit Trail Inquiry	A	TBHAGWAT	<input type="checkbox"/>
BA453	Reference Code Directory	R	SRENJ	<input type="checkbox"/>
BA453	Reference Code Directory	R	SRENJ	<input type="checkbox"/>
LN623	Provision code wise details report	R	TRENJ	<input type="checkbox"/>
BA77H	Audit Trail Header Report	R	TPARTHA	<input type="checkbox"/>
BA77H	Audit Trail Header Report	R	TDEVTD2	<input type="checkbox"/>
BA77E	Audit Trail Exhaustive Report	R	TDEVTD2	<input type="checkbox"/>
BA77D	Audit Trail Detail Report	R	TDEVTD2	<input type="checkbox"/>
BA77H	Audit Trail Header Report	R	TDEVTD2	<input type="checkbox"/>
ST051	Outstanding Instruments	R	TVINAY	<input type="checkbox"/>
AT001	Audit Trail Inquiry	A	TANCOOP	<input type="checkbox"/>
BA77H	Audit Trail Header Report	R	TNELSON	<input type="checkbox"/>
ST209	OCC Realisation/Dishonored Report	R	TNAGAP	<input type="checkbox"/>
CH332	Transaction Limit Breached	R	TNEHA	<input type="checkbox"/>
SM114	List of Users By Category, Level	R	TESTUSER01	<input type="checkbox"/>
BA77H	Audit Trail Header Report	R	TRAGINI	<input type="checkbox"/>
BA77E	Audit Trail Exhaustive Report	R	TNEHA	<input type="checkbox"/>
BA77E	Audit Trail Exhaustive Report	R	TDHANESH	<input type="checkbox"/>

1 / 4 1 2 3 4

Card	Change Pin	Cheque	Cost Rate	Denomination	Instrument	Inventory	Pin Validation	Service Charge	Signature	Travellers Cheque
------	------------	--------	-----------	--------------	------------	-----------	----------------	----------------	-----------	-------------------

UDF OK Close Clear

Field Description

Column Name	Description
ID	<p>[Display]</p> <p>This column displays the ID of the advice or report for which the request has been maintained.</p> <p>The report ID is added and maintained in the Report Control Maintenance (Fast Path: BAM16) option.</p>
Report/ Advice Name	<p>[Display]</p> <p>This column displays the name of the advice/report for which the request has been maintained.</p>
R / A	<p>[Display]</p> <p>This column displays the displays if the request is maintained for an advice or a report.</p> <p>The options are:</p> <ul style="list-style-type: none"> • R - for a Report • A - for an Advice
User ID	<p>[Display]</p> <p>This column displays the user ID of the teller/supervisor who has placed the request for the advice/report.</p>
Select	<p>[Optional, Check Box]</p> <p>Select the check box to cancel the advice/report.</p>

3. Select the appropriate check box in the **Select** column.

Report Cancel All Tellers

Report Cancel All Tellers*

ID	Report/Advice Name	R/A	UserID	Select
CH334	Card Hold Details	R	TVINAY7	<input type="checkbox"/>
AT001	Audit Trail Inquiry	A	TBHAGW	<input type="checkbox"/>
AT001	Audit Trail Inquiry	A	TBHAGW	<input type="checkbox"/>
BA453	Reference Code Dire	R	SRENU	<input type="checkbox"/>
BA453	Reference Code Dire	R	SRENU	<input type="checkbox"/>
UN623 UN623	Provision code rise details report: Provision cod	R	TRENU TRENU	<input checked="" type="checkbox"/>
BA77H	Audit Trail Header Re	R	TPARTHA	<input type="checkbox"/>
BA77H	Audit Trail Header Re	R	TDEVTD2	<input type="checkbox"/>
BA77E	Audit Trail Exhaust	R	TDEVTD2	<input type="checkbox"/>
BA77D	Audit Trail Detail Repor	R	TDEVTD2	<input type="checkbox"/>
BA77H	Audit Trail Header Re	R	TDEVTD2	<input type="checkbox"/>
ST051	Outstanding Instrume	R	TVINAY	<input type="checkbox"/>
AT001	Audit Trail Inquiry	A	TANCOOP	<input type="checkbox"/>
BA77H	Audit Trail Header Re	R	TNELSON	<input type="checkbox"/>
ST209	OCC Realls	R	TNAGAP	<input type="checkbox"/>
CH332	Transaction Limit Br	R	TNEHA	<input type="checkbox"/>
SM114	List of Users B	R	TESTUS	<input type="checkbox"/>
BA77H	Audit Trail Header Re	R	TRAGINI	<input type="checkbox"/>
BA77E	Audit Trail Exhaust	R	TNEHA	<input type="checkbox"/>
BA77E	Audit Trail Exhaust	R	TDHANES	<input type="checkbox"/>

1 2 3 4

Card Change Pin Cheque Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

- Click the **Ok** button.
- The system will cancel all the teller's advice/report request. Click the **Close** button.

6.5. 7779 - Report Print All Tellers

Using this option you can view the advice/report status that is requested by all users through the **Report Request** (Fast Path: 7775) option. Once the report/advice is selected for viewing, it cannot be viewed again by using this option.

Definition Prerequisites

- BAM16 - Report Control Maintenance
- 7775 - Report Request

Modes Available

Not Applicable

To view the report and advice status

1. Type the fast path **7779** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Reports > Report Print All Tellers**.
2. The system displays the **Report Print All Tellers** screen.

Report Print All Tellers

Report Print All Tellers*

ID	Report/Advice Name	R/A	User ID	Select
CH334	Card Hold Details	R	TVINAY7	<input type="checkbox"/>
AT001	Audit Trail Inquiry	A	TBHAGWAT	<input type="checkbox"/>
AT001	Audit Trail Inquiry	A	TBHAGWAT	<input type="checkbox"/>
BA453	Reference Code Directory	R	SRENU	<input type="checkbox"/>
BA453	Reference Code Directory	R	SRENU	<input type="checkbox"/>
GL006	PROFIT and LOSS REPORT	R	TDEVGL2	<input type="checkbox"/>
LN623	Provision code wise details report	R	TRENU	<input type="checkbox"/>
BA77H	Audit Trail Header Report	R	TPARTHA	<input type="checkbox"/>
BA77H	Audit Trail Header Report	R	TDEVID2	<input type="checkbox"/>
BA77E	Audit Trail Exhaustive Report	R	TDEVID2	<input type="checkbox"/>
BA77D	Audit Trail Detail Report	R	TDEVID2	<input type="checkbox"/>
BA77H	Audit Trail Header Report	R	TDEVID2	<input type="checkbox"/>
ST051	Outstanding Instruments	R	TVINAY	<input type="checkbox"/>
AT001	Audit Trail Inquiry	A	TANCOOP	<input type="checkbox"/>
BA77H	Audit Trail Header Report	R	TNELSON	<input type="checkbox"/>
ST209	OCC Realisation/Dishonored Report	R	TNAGAP	<input type="checkbox"/>
CH332	Transaction Limit Breached	R	TNEHA	<input type="checkbox"/>
SM114	List of Users By Category, Level	R	TESTUSER01	<input type="checkbox"/>
BA77H	Audit Trail Header Report	R	TRAGINI	<input type="checkbox"/>
BA77E	Audit Trail Exhaustive Report	R	TNEHA	<input type="checkbox"/>

1 / 3 1 2 3

Card Change Pin Cheque Cost Rate Denomination Instrument Inventory Pin Validation Service Charge Signature Travellers Cheque

UDF OK Close Clear

Field Description

Column Name	Description
ID	[Display] This column displays the ID of the report or advice for which the request has been made.
Report/ Advice Name	[Display] This column displays the name of the report/advice for which the request has been made.
R / A	[Display] This column displays whether the request has been maintained for a report or an advice. The options are: <ul style="list-style-type: none"> • R - for a Report • A - for an Advice
User ID	[Display] This column displays the user ID of the teller/supervisor who has placed the request for the report/advice.
Select	[Optional, Check Box] Select the check box to view the report/advice.

3. Select the appropriate check box in the **Select** column.

Report Print All Tellers

Report Print All Tellers*

ID	Report/Advice Name	R/A	User ID	Select
CH334	Card Hold Details	R	TVINAY7	<input type="checkbox"/>
AT001	Audit Trail Inquiry	A	TBHAGWAT	<input type="checkbox"/>
AT001	Audit Trail Inquiry	A	TBHAGWAT	<input type="checkbox"/>
BA453	Reference Code Directory	R	SRENUJ	<input type="checkbox"/>
BA453	Reference Code Directory	R	SRENUJ	<input type="checkbox"/>
GL006	PROFIT and LOSS REPORT	R	TDEVGL2	<input checked="" type="checkbox"/>
LN623	Provision code wise details report	R	TRENUJ	<input type="checkbox"/>
BA77H	Audit Trail Header Report	R	TPARTHA	<input type="checkbox"/>
BA77H	Audit Trail Header Report	R	TDEVTD2	<input type="checkbox"/>
BA77E	Audit Trail Exhaustive Report	R	TDEVTD2	<input type="checkbox"/>
BA77D	Audit Trail Detail Report	R	TDEVTD2	<input type="checkbox"/>
BA77H	Audit Trail Header Report	R	TDEVTD2	<input type="checkbox"/>
ST051	Outstanding Instruments	R	TVINAY	<input type="checkbox"/>
AT001	Audit Trail Inquiry	A	TANCOOP	<input type="checkbox"/>
BA77H	Audit Trail Header Report	R	TNELSON	<input type="checkbox"/>
ST209	OCC Realisation/Dishonored Report	R	TNAGAP	<input type="checkbox"/>
CH332	Transaction Limit Breached	R	TNEHA	<input type="checkbox"/>
SM114	List of Users By Category, Level	R	TESTUSER01	<input type="checkbox"/>
BA77H	Audit Trail Header Report	R	TRAGINI	<input type="checkbox"/>
BA77E	Audit Trail Exhaustive Report	R	TNEHA	<input type="checkbox"/>

1 / 3 1 2 3

Card	Change Pin	Cheque	Cost Rate	Denomination	Instrument	Inventory	Pin Validation	Service Charge	Signature	Travellers Cheque
------	------------	--------	-----------	--------------	------------	-----------	----------------	----------------	-----------	-------------------

UDF OK Close Clear

- Click the **OK** button.
- The system displays the report.

Report

Head Office	
Term Loan_015 Advice of Disbursement	
Mr BRIAN JOHNSON 123 PPP AHMEDABAD GOA 5646545 101	
Account Number	: 0000000019257
Date opened	: 15/11/2007
Sanctioned Amount	: INR 25,000.00
Dear Sir/Madam,	
We are pleased to inform you that under the terms and conditions of your loan account number 0000000019257 the following amount has been disbursed as detailed below.	
Number of Disbursements: 1	
Gross Disbursed Amount:	INR 29,406.72
Disbursement Date: 31/12/2007	
Total Deductions: INR 4407	
(Deduct):	4,406.72
Yearly Fee (Debit):	900.00
Net Amount Disbursed :	25,000.00
Credit A/c Number :	0000000008086
Cheque Number :	
Do contact us for any clarification.	
Assuring you of our best service at all times.	
Yours Faithfully	

6. Select the **Print** option from the **File** menu.
7. The system displays the **Print** dialog box.
8. Select the appropriate parameters and click the **Print** button.
9. Click the **Close** button.

6.6. 7778 - Advice/Report Status Inquiry

Using this option the advice /reports are displayed which are requested by the user login Id, through the **Reports Request** (Fast Path: 7775) option. The user who has requested the advices/reports can view the status and generate the advices or reports.

The supervisor can view all the report/advice requests of any teller associated under his/her supervision. In this case, select the teller from the drop-down list whose transaction details you want to view.

For more information, please refer to the respective Module wise Reports Manual.

Definition Prerequisites

- BAM16 - Report Control Maintenance
- 7775 - Report Request

Modes Available

Not Applicable

To view the advice/report status

1. Type the fast path **7778** and click **Go** or navigate through the menus to **Transaction Processing > Internal Transactions > Reports > Advice/Report Status Inquiry**.
2. The system displays the **Advice/Report Status Inquiry** screen.

Advice/Report Status Inquiry

Advice/Report Status Inquiry*

Teller ID :

TD0C1

ID	Report/Advice Name	R/A	Select
----	--------------------	-----	--------

0.00

Card

Change Pin

Cheque

Cost Rate

Denomination

Instrument

Inventory

Pin Validation

Service Charge

Signature

Travellers Cheque

UDF

View

Close

Clear

Field Description

Field Name	Description
Teller ID	<div>[Display]</div> <div>This field displays the user ID of the teller who has logged in.</div> <div>Only those report generation requests performed by the teller who has logged in will be displayed.</div> <div>In case of a supervisor login, the supervisor can view all the report/advice requests of any teller associated under his/her supervision.</div> <div>In this case, select the teller whose transaction details you want to view, from the drop-down list.</div> <div>This field is editable, in case of a supervisor login.</div>

Column Name	Description
ID	<p>[Display]</p> <p>This column displays the ID of the advice or report for which the request has been made.</p> <p>The report ID is added and maintained in the Report Control Maintenance (Fast Path: BAM16) option.</p>
Report/ Advice Name	<p>[Display]</p> <p>This column displays the name of the advice/report for which the request has been made.</p>
R / A	<p>[Display]</p> <p>This column displays whether the request has been maintained for an advice or a report.</p> <p>The options are:</p> <ul style="list-style-type: none"> • R - for a Report • A - for an Advice
Select	<p>[Optional, Check Box]</p> <p>Select the check box to view the corresponding advice/report.</p>

3. Select the appropriate check box in the **Select** column

Advice/Report Status Inquiry

Advice/Report Status Inquiry*

Teller ID : TDOCI

ID	Report/Advice Name	R/A	Select
SM106	User List	R	<input checked="" type="checkbox"/>

1

/1

1

Card

Change Pin

Cheque

Conv Rate

Denomination

Instrument

Inventory

Pin Validation

Service Charge

Signature

Travellers Cheque

UDF

View

Close

Clear

- 4. Click the **View** button.
- 5. The system displays the report.

Report

Bank : 9999 DemoBank		LISFLEXCUBERS						Run Date : 10:38 AM08		
Op. Id : TDOC1		For: 29-Feb-2008						Report No: SM106/		
User No. User Name	User Id	Profile St. Date	Profile End Date	Brn Code	Lang Code	Host Temp1	Branch Temp1	Access Code	Category	User Level
645 First teller	GEFUONLY	03-07-2007	01-01-2049	9999	ENG	19	19	90	OT	15
507 First Supervisor	SABHAYP	03-07-2007	01-01-2049	9999	ENG	16	16	90	OT	50
283 First Supervisor	SABHIJEET	03-07-2007	01-01-2049	9999	ENG	16	16	90	OT	50
*** End of Report ***										

6. Select the **Print** option from the **File** menu.
7. The system displays the **Print** dialog box.
8. Select the appropriate parameters and click the **OK** button.