

SPARC: Oracle® Solaris Cluster Data Service for Oracle VM Server for SPARC Guide

Part No: E69336
August 2018

ORACLE®

Part No: E69336

Copyright © 2008, 2018, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Référence: E69336

Copyright © 2008, 2018, Oracle et/ou ses affiliés. Tous droits réservés.

Ce logiciel et la documentation qui l'accompagne sont protégés par les lois sur la propriété intellectuelle. Ils sont concédés sous licence et soumis à des restrictions d'utilisation et de divulgation. Sauf stipulation expresse de votre contrat de licence ou de la loi, vous ne pouvez pas copier, reproduire, traduire, diffuser, modifier, accorder de licence, transmettre, distribuer, exposer, exécuter, publier ou afficher le logiciel, même partiellement, sous quelque forme et par quelque procédé que ce soit. Par ailleurs, il est interdit de procéder à toute ingénierie inverse du logiciel, de le désassembler ou de le décompiler, excepté à des fins d'interopérabilité avec des logiciels tiers ou tel que prescrit par la loi.

Les informations fournies dans ce document sont susceptibles de modification sans préavis. Par ailleurs, Oracle Corporation ne garantit pas qu'elles soient exemptes d'erreurs et vous invite, le cas échéant, à lui en faire part par écrit.

Si ce logiciel, ou la documentation qui l'accompagne, est livré sous licence au Gouvernement des Etats-Unis, ou à quiconque qui aurait souscrit la licence de ce logiciel pour le compte du Gouvernement des Etats-Unis, la notice suivante s'applique :

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

Ce logiciel ou matériel a été développé pour un usage général dans le cadre d'applications de gestion des informations. Ce logiciel ou matériel n'est pas conçu ni n'est destiné à être utilisé dans des applications à risque, notamment dans des applications pouvant causer un risque de dommages corporels. Si vous utilisez ce logiciel ou ce matériel dans le cadre d'applications dangereuses, il est de votre responsabilité de prendre toutes les mesures de secours, de sauvegarde, de redondance et autres mesures nécessaires à son utilisation dans des conditions optimales de sécurité. Oracle Corporation et ses affiliés déclinent toute responsabilité quant aux dommages causés par l'utilisation de ce logiciel ou matériel pour des applications dangereuses.

Oracle et Java sont des marques déposées d'Oracle Corporation et/ou de ses affiliés. Tout autre nom mentionné peut correspondre à des marques appartenant à d'autres propriétaires qu'Oracle.

Intel et Intel Xeon sont des marques ou des marques déposées d'Intel Corporation. Toutes les marques SPARC sont utilisées sous licence et sont des marques ou des marques déposées de SPARC International, Inc. AMD, Opteron, le logo AMD et le logo AMD Opteron sont des marques ou des marques déposées d'Advanced Micro Devices. UNIX est une marque déposée de The Open Group.

Ce logiciel ou matériel et la documentation qui l'accompagne peuvent fournir des informations ou des liens donnant accès à des contenus, des produits et des services émanant de tiers. Oracle Corporation et ses affiliés déclinent toute responsabilité ou garantie expresse quant aux contenus, produits ou services émanant de tiers, sauf mention contraire stipulée dans un contrat entre vous et Oracle. En aucun cas, Oracle Corporation et ses affiliés ne sauront être tenus pour responsables des pertes subies, des coûts occasionnés ou des dommages causés par l'accès à des contenus, produits ou services tiers, ou à leur utilisation, sauf mention contraire stipulée dans un contrat entre vous et Oracle.

Accès aux services de support Oracle

Les clients Oracle qui ont souscrit un contrat de support ont accès au support électronique via My Oracle Support. Pour plus d'informations, visitez le site <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> ou le site <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> si vous êtes malentendant.

Contents

Using This Documentation	9
1 SPARC: Installing and Configuring HA for Oracle VM Server	11
SPARC: Installing and Configuring HA for Oracle VM Server	12
SPARC: HA for Oracle VM Server Overview	12
SPARC: Planning the HA for Oracle VM Server Installation and Configuration	13
Configuration Guidelines	13
▼ SPARC: How to Configure Oracle VM Server for SPARC to Reset for Control Domain Failures	14
SPARC: Installing and Configuring Oracle VM Server for SPARC	16
▼ SPARC: How to Install the Oracle VM Server for SPARC Software	16
▼ SPARC: How to Enable the Oracle VM Server for SPARC Instances to Run in a Cluster	16
Installing the HA for Oracle VM Server Package	17
▼ How to Install the HA for Oracle VM Server Package	17
SPARC: Registering and Configuring HA for Oracle VM Server	18
▼ SPARC: How to Configure HA for Oracle VM Server	18
▼ SPARC: How to Remove an HA for Oracle VM Server Resource From a Failover Resource Group	22
SPARC: Verifying the Installation and Configuration of Oracle VM Server for SPARC	22
▼ SPARC: How to Verify the HA for Oracle VM Server Installation and Configuration	22
SPARC: Tuning the HA for Oracle VM Server Fault Monitor	23
Resource Properties	23
Probing Algorithm and Functionality	23
Operations of the Oracle VM Server for SPARC Probe	24
SPARC: Debugging HA for Oracle VM Server	25
▼ SPARC: How to Activate Debugging for HA for Oracle VM Server	25

Contents

Index	27
--------------------	-----------

Tables

TABLE 1	Tasks for Installing and Configuring HA for Oracle VM Server	12
----------------	--	----

Using This Documentation

- **Overview** – Describes the Oracle Solaris Cluster HA for Oracle VM Server for SPARC software.
- **Audience** – Experienced system administrators with extensive knowledge of Oracle software and hardware.
- **Required knowledge** – Knowledge of the Oracle Solaris operating system, of Oracle Solaris Cluster software, and expertise with the volume manager software that is used with Oracle Solaris Cluster software.

This document is not to be used as a planning or presales guide.

Product Documentation Library

Documentation and resources for this product and related products are available at http://www.oracle.com/pls/topic/lookup?ctx=E69294_01.

Feedback

Provide feedback about this documentation at <http://www.oracle.com/goto/docfeedback>.

SPARC: Installing and Configuring HA for Oracle VM Server

This chapter explains how to install and configure Oracle Solaris Cluster HA for Oracle VM Server for SPARC (HA for Oracle VM Server) software and contains the following sections:

- “[Installing and Configuring HA for Oracle VM Server](#)” on page 12
- “[HA for Oracle VM Server Overview](#)” on page 12
- “[Planning the HA for Oracle VM Server Installation and Configuration](#)” on page 13
- “[Installing and Configuring Oracle VM Server for SPARC](#)” on page 16
- “[Installing the HA for Oracle VM Server Package](#)” on page 17
- “[Registering and Configuring HA for Oracle VM Server](#)” on page 18
- “[Verifying the Installation and Configuration of Oracle VM Server for SPARC](#)” on page 22
- “[Tuning the HA for Oracle VM Server Fault Monitor](#)” on page 23
- “[Debugging HA for Oracle VM Server](#)” on page 25

Note - You can also use the Oracle Solaris Cluster Manager browser interface to configure this data service. In the Tasks panel of Oracle Solaris Cluster Manager, click Oracle VM Server for SPARC to start the configuration wizard. For log-in instructions, see [Chapter 12, “Using the Oracle Solaris Cluster Manager Browser Interface” in Administering an Oracle Solaris Cluster 4.4 Configuration](#).

This wizard requires that all cluster nodes have the same root password.

SPARC: Installing and Configuring HA for Oracle VM Server

The following table summarizes the tasks for installing and configuring HA for Oracle VM Server and provides cross-references to detailed instructions for performing these tasks. Perform the tasks in the order that they are listed in the table.

TABLE 1 Tasks for Installing and Configuring HA for Oracle VM Server

Task	Instructions
Plan the installation.	“Planning the HA for Oracle VM Server Installation and Configuration” on page 13
Install and configure the Oracle VM Server for SPARC software.	“Installing and Configuring Oracle VM Server for SPARC” on page 16
Install HA for Oracle VM Server packages.	“Installing the HA for Oracle VM Server Package” on page 17
Register and configure HA for Oracle VM Server resources.	“Registering and Configuring HA for Oracle VM Server” on page 18
Verify the HA for Oracle VM Server installation and configuration.	“Verifying the Installation and Configuration of Oracle VM Server for SPARC” on page 22
Tune the HA for Oracle VM Server fault monitor.	“Tuning the HA for Oracle VM Server Fault Monitor” on page 23
Debug HA for Oracle VM Server.	“Debugging HA for Oracle VM Server” on page 25

SPARC: HA for Oracle VM Server Overview

The Oracle Solaris Cluster HA for Oracle VM Server for SPARC (HA for Oracle VM Server) data service provides the ability to split a single physical system into multiple, independent virtual systems. This is achieved by an additional software application in the firmware layer, interposed between the operating system and the hardware platform called the hypervisor. It abstracts the hardware and can expose or hide various resources, allowing for the creation of resource partitions that can operate as discrete systems, complete with virtual CPU, memory, and I/O devices.

You create the logical domain on any one of the nodes of the cluster. However the services configuration must be identical on all the potential primary nodes. The domain configuration is retrieved by the `ldm list-constraints -x ldom` command and stored in the CCR. This globally accessible information is used by the HA for Oracle VM Server agent to create or destroy the domain on the node where the resource group is brought online or offline.

HA for Oracle VM Server provides a mechanism for orderly startup and shutdown, fault monitoring, and automatic failover of the Oracle VM Server for SPARC logical domain service.

The Oracle VM Server for SPARC component is protected by the HA for Oracle VM Server data service.

Note the following points regarding support for the SR-IOV device in the HA for Oracle VM Server data service:

- An SR-IOV device is not supported for live migration of the HA for Oracle VM Server data service. Contact your Oracle support representative to learn whether support for the SR-IOV feature becomes available.
- An SR-IOV device is supported for normal migration of the HA for Oracle VM Server data service. This support requires that the SR-IOV device path is identical on all potential primaries of the data service's resource group.

SPARC: Planning the HA for Oracle VM Server Installation and Configuration

This section contains the information you need to plan your HA for Oracle VM Server installation and configuration.

Configuration Guidelines

Observe the following configuration guidelines that apply only to HA for Oracle VM Server.

For restrictions that apply to all data services, see the [Oracle Solaris Cluster 4.4 Release Notes](#).

- **HA for Oracle VM Server configuration** – Oracle VM Server for SPARC can be configured only as a failover data service and not as a scalable data service. It can be configured only in the global zone.
- **HA for Oracle VM Server virtual disks** – The Oracle VM Server for SPARC virtual disk back end can be of any storage or file system that is supported by Oracle Solaris Cluster software. This includes cluster file systems (Global UFS or Global ZFS), raw disk, NFS, iSCSI, and SAN LUNs. The back end is exported through the virtual disk server of the control domain to a domain as a full disk and is visible to the Oracle Solaris installation software inside the logical domain. Virtual disks from non-control domains are not supported.
- **Multiple domain migration** Oracle VM Server for SPARC 3.5 has the following restriction:

While a migration is in progress on a machine, any operation that might result in the modification of the state or configuration of the domain being migrated is blocked. All

operations on the domain itself, as well as operations such as bind and stop on other domains on the machine, are blocked.

The implication is that it is not possible to switch a resource group that has multiple resources of type SUNW.l dom, or multiple resource groups where each resource group has a resource of type SUNW.l dom, at the same time as the domain migration will be blocked. Instead, plan to manually serialise domain migration between Oracle Solaris Cluster nodes.

If a resource group has multiple resources of type SUNW.l dom then specify a resource dependency between those resources. If there are multiple resource groups where each resource group has a resource of type SUNW.l dom then plan to switch one resource group at a time.

- **Live migration and warm migration** – HA for Oracle VM Server software supports Oracle VM Server for SPARC live migration and warm migration. For more information, see your Oracle VM Server for SPARC documentation.

In some cases where the cluster cannot determine the target node to which the HA for Oracle VM Server resource group is migrating, it uses an ordinary resource group switchover instead of using live migration. In such cases, the logical domain shuts down on its current node and then boots on its new node. To achieve live migration, relocate the HA for Oracle VM Server resource group by using the `clresourcegroup switch` command explicitly on the resource group, rather than depending on node evacuation or strong resource group affinities to move the resource group.

You can specify the `Abort_migration` extension property to specify the behavior of the `clrg switchover -n ldom-rg` command for a resource group that contains a SUNW.l dom resource. For more information, see the [SUNW.l dom\(7\)](#) manpage.

Live migration is supported only for cluster file systems (Global UFS or Global ZFS), raw disk,NFS, iSCSI, or SAN LUNs, as live migration requires that storage is accessible to all potential primary nodes simultaneously.

Oracle VM Server for SPARC data service creates symlinks for the `libschost.so.1` shared object and uses this during live migration of guest domain.

```
# ln -s /usr/cluster/lib/libschost.so.1 /usr/lib/secure/libschost.so.1
# ln -s /usr/cluster/lib/64/libschost.so.1 /usr/lib/secure/64/libschost.so.1
```

▼ SPARC: How to Configure Oracle VM Server for SPARC to Reset for Control Domain Failures

The failure policy settings on the primary domain determine the action to be taken on the logical domain when there is a primary domain failures. When configured to failure-

policy=reset, the logical domain would panic when the primary domain fails. If the failure policy is not set to reset on all the primary domains, the resource creation would fail. You must set the master-slave domain dependency and auto-boot? variable to appropriate values. Perform the following steps on the node where the ldg0 logical domain is created:

1. Set the domain failure policy to reset.

```
# ldm set-domain failure-policy=reset primary
# ldm list -o domain primary
NAME          STATE      FLAGS    UTIL
primary       active     -n-cv-    0.6%
SOFTSTATE
Solaris running

HOSTID
0x84d4a2ce

CONTROL
failure-policy=reset

DEPENDENCY
master=
```

2. Configure the master-slave domain dependency.

```
# ldm set-domain master=primary ldg0
```

3. Set the auto-boot? variable to false.

```
# ldm set-var auto-boot?=false ldg0
# ldm list -o domain ldg0
NAME          STATE      FLAGS    UTIL
ldg0          active     n---    0.1%
SOFTSTATE
Solaris running

HOSTID
0x84f8a040

CONTROL
failure-policy=reset

DEPENDENCY
master=primary

VARIABLES
```

```
auto-boot?=false
boot-device=vdisk1
keyboard-layout=US-English
```

The `auto-boot?` variable should be set to false on the guest domain. Do not change `auto-boot?` to true while the guest domain is being managed by a `SUNW.ldom` resource.

SPARC: Installing and Configuring Oracle VM Server for SPARC

This section contains the procedures you need to install and configure an Oracle VM Server for SPARC logical domain.

▼ SPARC: How to Install the Oracle VM Server for SPARC Software

1. **On a cluster member, assume the `root` role or assume a role that provides `solaris.cluster.modify` authorization.**
2. **Go to <http://www.oracle.com/technetwork/server-storage/vm/downloads/index.html?ssSourceSiteId=ocomen>.**

Follow instructions to download and install Oracle VM Server for SPARC software.

▼ SPARC: How to Enable the Oracle VM Server for SPARC Instances to Run in a Cluster

1. **Become superuser or assume a role that provides `solaris.cluster.admin` authorization on one of the nodes in the cluster that will host the Oracle VM Server for SPARC logical domain.**
2. **Register the `SUNW.HAStoragePlus` resource type.**

```
# clresourcetype register SUNW.HAStoragePlus
```

3. **Create a failover resource group.**

```
# clresourcegroup create LDom-failover-rg
```

4. **(If using a cluster file system or a highly available local file system) Create an HAStoragePlus resource for the logical domain Virtual Disk Storage.**

```
# clresource create -g LDom-failover-rg \
-t SUNW.HAStoragePlus \
-p FileSystemMountPoints=LDom-mount-points \
LDom-has-resource
```

5. **Enable the failover resource group that now includes the logical domain disk storage resources.**

```
# clresourcegroup online -M -n current-node LDom-failover-rg
```

Installing the HA for Oracle VM Server Package

If you did not install the HA for Oracle VM Server package during your initial Oracle Solaris Cluster installation, perform this procedure to install the package.

▼ How to Install the HA for Oracle VM Server Package

Perform this procedure on each cluster node where you want the HA for Oracle VM Server software to run.

1. **On the cluster node where you are installing the data service package, assume the root role.**
2. **Ensure that the data service package is available from the configured publisher and that the `solaris` and `ha-cluster` publishers are valid.**

```
# pkg list -a ha-cluster/data-service/ha-ldom
# pkg publisher
PUBLISHER          TYPE    STATUS   P  LOCATION
solaris            origin  online   F  solaris-repository
ha-cluster         origin  online   F  ha-cluster-repository
```

For information about setting the `solaris` publisher, see “[Adding, Modifying, or Removing Package Publishers](#)” in *Updating Systems and Adding Software in Oracle Solaris 11.4*.

Tip - Use the -nv options whenever you install or update to see what changes will be made, such as which versions of which packages will be installed or updated and whether a new BE will be created.

If you do not get any error messages when you use the -nv options, run the command again without the -n option to actually perform the installation or update. If you do get error messages, run the command again with more -v options (for example, -nvv) or more of the package FMRI pattern to get more information to help you diagnose and fix the problem. For troubleshooting information, see [Appendix A, “Troubleshooting Package Installation and Update,” in *Updating Systems and Adding Software in Oracle Solaris 11.4*](#).

3. Install the HA for Oracle VM Server software package.

```
# pkg install ha-cluster/data-service/ha-ldom
```

4. Verify that the package installed successfully.

```
$ pkg info ha-cluster/data-service/ha-ldom
```

Installation is successful if output shows that State is Installed.

5. Perform any necessary updates to the Oracle Solaris Cluster software.

For instructions about updating your software, see [Chapter 10, “Updating Software Packages” in *Updating Your Oracle Solaris Cluster 4.4 Environment*](#).

SPARC: Registering and Configuring HA for Oracle VM Server

▼ SPARC: How to Configure HA for Oracle VM Server

Before You Begin Install the data service packages during your initial Oracle Solaris Cluster installation.

If you did not install the HA for Oracle VM Server packages as part of your initial Oracle Solaris Cluster installation, go to [“Installing the HA for Oracle VM Server Package” on page 17](#).

1. Assume the **root** role or a role that provides **solaris.cluster.modify** and **solaris.cluster.admin** authorization on the node in the cluster that hosts the Oracle VM Server for SPARC logical domain.
2. Register the **SUNW.ldom** resource type.

```
# clresourcetype register SUNW.ldom
```

3. (Optional) You can plan to use the live migration with or without the use of SSL certificates.

- If you plan to use live migration with SSL certificates, for resource type version 8 or later, you must use the SSL certificates authentication for the live migration of guest domain. You must first configure the SSL certificates on all potential primary nodes of the resource group that will contain the resource type **SUNW.ldom:8** or later. To perform SSL certificates authentication, you must set the value of the **Use_SSL_Certificate=TRUE**.

For more details, see [Configuring SSL Certificates for Migration](#).

- (Optional) If you plan to use live migration without using SSL certificates, configure the password.
- For the resource type version 6 or later, create a private string named **resourcegroup_resource_ldompasswd** to store the target host password that is required for guest domain migration.

Type the following command on any one node in the cluster:

```
# /usr/cluster/bin/clpstring create -b rsname \
-t rgname_rsname_ldompasswd
Enter string value:
Enter string value again:
```

where **rgname** and **rsname** are the resource group and resource name for the **SUNW.ldom** resource that is created.

- For resource type version 5 or earlier, the **Password_file** property is required during resource creation. Create a password file owned by **root** with read only permission to store the target host password required for guest domain migration.

Type the following command on each of the Oracle Solaris Cluster nodes that would host the logical domain resource:

```
# echo password > /var/cluster/.ldg1_passwd
```

```
# /usr/bin/chown root:root /var/cluster/.ldg1_passwd  
# /usr/bin/chmod 400 /var/cluster/.ldg1_passwd
```

where `/var/cluster/.ldg1_passwd` is the password file for guest domain `ldg1`.
`password` is the target node root password used for live migration.

4. Create an Oracle VM Server for SPARC logical domain resource in the failover resource group.

- If you are not using live migration, set `Migration_type=NORMAL` during resource creation and do not specify the `Password_file` property.

```
# clresource create -g ldg1-rg \  
-t SUNW.ldom \  
-p Domain_name=ldg1 \  
-p Miration_type=NORMAL \  
-p Resource_dependencies_offline_restart=ldg1-haspr-s \  
ldg1
```

- If you are using live migration, set `Migration_type=MIGRATE` during resource creation and specify `Password_file` for resource type version 5 or earlier.

Note - The `Password_file` property is obsolete for resource type version 6 or later.

For resource type version 5 or earlier, type the following command:

```
# clresource create -g ldg1-rg \  
-t SUNW.ldom \  
-p Domain_name=ldg1 \  
-p Miration_type=MIGRATE \  
-p Password_file=/var/cluster/.ldg1_passwd \  
-p Resource_dependencies_offline_restart=ldg1-haspr-s \  
ldg1
```

Note - The `Use_SSL_Certificate` property is only available for resource type version 8 or later. If you have configured both SSL certificates mechanism and private string mechanism for live migration, the value of `Use_SSL_Certificate` decides which mechanism to use.

For resource type version 6 or later, type the following command:

```
# clresource create -g ldg1-rg \  
-t SUNW.ldom \  
-p Domain_name=ldg1 \  
-p Miration_type=MIGRATE \  
-p Resource_dependencies_offline_restart=ldg1-haspr-s \  
ldg1
```

ldg1

5. For resource type version 5 or earlier, if an encrypted password is required for the logical domain migration, you must do the following:

- a. Insert the word encrypted into the file you specify with the **Password_file** extension property when creating the resource.

```
# echo "encrypted" > /var/cluster/.ldg1_passwd
```

- b. Assume the root role and create an encrypted password.

In the following example, the root password for the primary domain, *password*, is being encrypted and *ldg1* reflects the logical domain name.

```
node1# dd if=/dev/urandom of=/var/cluster/ldom_key bs=16 count=1
node1# chmod 400 /var/cluster/ldom_key
node1# echo password | /usr/sfw/bin/openssl enc -aes128 -e \
-pass file:/var/cluster/ldom_key -out /opt/SUNWscxvm/.ldg1_passwd
node1# chmod 400 /opt/SUNWscxvm/.ldg1_passwd
```

- c. Verify that the encrypted password can be decrypted.

```
node1# /usr/sfw/bin/openssl enc -aes128 -d -pass file:/var/cluster/ldom_key \
-in /opt/SUNWscxvm/.ldg1_passwd
```

- d. Repeat the preceding steps on all Oracle Solaris Cluster nodes that host the logical domain service.
- e. Create or update the resource and set the **Password_file** property to the path provided in Step a.

Note - You can perform this step only when the resource is disabled.

```
# clresource set -p Password_file=/var/cluster/.ldg1_passwd LDom-guest-domain-
resource
```

6. Enable each logical domain resource.

Repeat this step for each logical domain instance, if multiple instances were created.

```
# clresource status
# clresource enable logical-guest-domain-resource
```

▼ SPARC: How to Remove an HA for Oracle VM Server Resource From a Failover Resource Group

1. Assume the **root** role or assume a role that provides `solaris.cluster.modify` and `solaris.cluster.admin` RBAC authorizations.
2. Disable and remove the resource that is used by the HA for Oracle VM Server data service.

```
# clresource disable resource
# clresource delete resource
```

Note - If the resource used a private string `rgname_rsname_ldompasswd` for live migration, the deletion of resource will also result in the deletion of the private string.

SPARC: Verifying the Installation and Configuration of Oracle VM Server for SPARC

▼ SPARC: How to Verify the HA for Oracle VM Server Installation and Configuration

1. As the **root** role, log in to the node that currently hosts the resource group that contains the Oracle VM Server for SPARC logical domain resource.
2. Switch the logical domain resource group to another cluster member.

```
# clresourcegroup switch -n node logical-domain
```

3. Verify the status of the logical domain instance.

```
# ldm list-domain logical-domain
NAME          STATE    FLAGS   CONS   VCPU  MEMORY   UTIL   UPTIME
ldg           active   n---   5000    4     2G        25%   2s
```

4. Repeat the preceding steps until you have tested all the potential nodes on which the logical domain can run.

SPARC: Tuning the HA for Oracle VM Server Fault Monitor

This section describes the HA for Oracle VM Server fault monitor's probing algorithm or functionality, and states the conditions, messages, and recovery actions associated with unsuccessful probing.

Note - For any maintenance or modification activities on the domain, you must disable monitoring, perform maintenance tasks, and then re-enable the resource monitor.

For conceptual information about fault monitors, see the [Concepts for Oracle Solaris Cluster 4.4](#).

Resource Properties

The HA for Oracle VM Server logical domain fault monitor uses the resource properties specified in the resource type SUNW.ldom. Refer to the [SUNW.ldom\(7\)](#) man page for a complete list of resource properties used.

Probing Algorithm and Functionality

HA for Oracle VM Server is controlled by the extension properties that control the probing frequency. The default values of these properties determine the preset behavior of the fault monitor and are suitable for most Oracle Solaris Cluster installations. You can modify this preset behavior by performing the following actions:

- Setting the interval between fault monitor probes (`Thorough_probe_interval`)
- Setting the timeout for fault monitor probes (`Probe_timeout`)
- Setting the number of times the fault monitor attempts to restart the resource (`Retry_count`)

The HA for Oracle VM Server fault monitor checks the domain status within an infinite loop. During each cycle, the fault monitor checks the domain state and reports either a failure or success.

If the fault monitor is successful, it returns to its infinite loop and continues the next cycle of probing and sleeping.

If the fault monitor reports a failure, a request is made to the cluster to restart the resource. If the fault monitor reports another failure, another request is made to the cluster to restart the

resource. This behavior continues whenever the fault monitor reports a failure. If successive restarts exceed the `Retry_count` within the `Thorough_probe_interval`, a request is made to fail over the resource group onto a different node.

Operations of the Oracle VM Server for SPARC Probe

- The probe checks the domain state every 60 seconds by using the `ldm list-domain` command.
- The `ldm list-domain` command produces a status line for the domain and is accurate at the instant that the command executes.
- The status modes that are considered to be normal operational modes are as follows: active, suspending, resuming, suspended, and starting. Whenever the `ldm` command reports these status modes, the probe considers that the domain is operating in an acceptable mode.
- The status modes that are considered to be restartable modes are as follows: inactive and stopping. These modes are not considered acceptable and if one of these modes is encountered, the probe requests a restart of the resource.
- The probe also requests a resource to restart if any unknown status modes are reported by the `ldm` command.
- If the logical domain configuration has changed, the probe updates this information to the CCR in the next probe cycle. Alternatively, you can perform the following steps to update the changed configuration to the CCR immediately:

1. Make a dummy update to the resource. For example:

```
# clresource set \
-p R_DESCRIPTION="Oracle Solaris Cluster HA for Oracle VM Server SPARC Guest
Domains - Modified" \
ldg1-rs
```

2. Verify whether the configuration change was successfully done.

From the node where the guest domain is online, type the following commands, where `ld1-rs` is the logical domain resource name and `ldg1` is the guest domain name:

```
# (/usr/cluster/lib/sc/ccradm showkey --key xml_ldg1-rs ldom_domain_config | \
xmllint --format -) > /var/tmp/ldg1_ccr.xml
# ldm list-constraints -x ldg1 > /var/tmp/ldg1_current.xml
# diff /var/tmp/ldg1_current.xml /var/tmp/ldg1_ccr.xml
```

- The probe runs the user-supplied script or binary provided for `plugin_probe`. If this process fails, then the probe will restart the logical domain resource. The exit status of the

`plugin_probe` command is used to determine the severity of the failure of the application. This exit status, called the `plugin_probe` status, must be an integer between `0` (for success) and `100` (for complete failure). The `plugin_probe` status can also be a special value of `201` which results in immediate failover of the application unless `Failover_enabled` is set to `FALSE`.

- If the logical domain resource is repeatedly restarted and subsequently exhausts the `Retry_count` within the `Retry_interval`, then a failover is initiated for the resource group onto another node if `Failover_enabled` is set to `TRUE`.

SPARC: Debugging HA for Oracle VM Server

HA for Oracle VM Server has a extension property named `Debug_level` that enables you to activate debugging for Oracle VM Server for SPARC logical domain resources.

▼ SPARC: How to Activate Debugging for HA for Oracle VM Server

1. Determine whether debugging for HA for Oracle VM Server is active.

```
# grep daemon /etc/syslog.conf
*.err;kern.debug;daemon.notice;mail.crit      /var/adm/messages
*.alert;kern.err;daemon.err                   operator
#
```

If debugging is active, `daemon.debug` is set in the file `/etc/syslog.conf`.

If debugging is inactive, `daemon.notice` is set in the file `/etc/syslog.conf` of the appropriate node.

2. If debugging is inactive, edit the `/etc/syslog.conf` file in the appropriate node to change `daemon.notice` to `daemon.debug`.
3. Confirm that debugging for HA for Oracle VM Server is active.

```
# grep daemon /etc/syslog.conf
*.err;kern.debug;daemon.debug;mail.crit      /var/adm/messages
*.alert;kern.err;daemon.err                   operator
#
```

4. Restart the `syslogd` daemon in the global zone.

```
# svcadm refresh svc:/system/system-log:default
```

5. Set the property `Debug_level` to level 2.

```
# clresource set -p Debug_level=2 logical-domain-resource
```

For more information about the `Debug_level` extension property and permissible values, see the [SUNW.ldom\(7\)](#) man page.

Note - To deactivate debugging, repeat these steps, changing `daemon.debug` to `daemon.notice` and changing the `Debug_level` property to 0.

Index

C

configuration restrictions, 13
configuring
 HA for Oracle VM Server
 using the Oracle Solaris Cluster Manager
 wizard, 11

D

debugging
 HA for Oracle VM Server, 25

F

functionality, 23

H

HA for Oracle VM Server
 debugging, 25
 installing, 17
 overview, 12
 software package, installing, 17

I

installing
 HA for Oracle VM Server, 17
 Oracle VM Server for SPARC software, 16

L

live migration, 14

O

operations
 Oracle VM Server for SPARC probe, 24
Oracle Solaris Cluster Manager
 configuration wizard, 11
Oracle Solaris Cluster software
 publisher, 17, 17
overview
 HA for Oracle VM Server, 12
 installation, 12

P

package, 17
planning
 HA for Oracle VM Server, 13
probing algorithm, 23
publisher
 Oracle Solaris Cluster software, 17, 17

R

registering and configuring, 18
reset for control domain failures
 configuration, 14
resource properties, 23
resources
 Oracle VM Server for SPARC application
 debugging, 25

S

software installation

Oracle VM Server for SPARC, 16
software package, 17

T

tuning fault monitor, 23

V

verifying
 Oracle VM Server for SPARC configuration, 22

W

warm migration, 14, 20
wizard
 Oracle Solaris Cluster Manager, 11