

**Oracle® Communications  
Diameter Signaling Router**

Subscriber Database Server User's Guide

Release 8.1

**E85614 Revision 01**

July 2017

Oracle Communications Diameter Signaling Router Subscriber Database Server User's Guide, Release 8.1  
Copyright © 2011, 2017, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

# Table of Contents

<b>Chapter 1: Introduction.....</b>	<b>9</b>
Revision History.....	10
The SDS Help System.....	10
Scope and Audience.....	10
Manual organization.....	10
Documentation Admonishments.....	11
Related Publications.....	11
Locate Product Documentation on the Oracle Help Center Site.....	11
Customer Training.....	12
My Oracle Support (MOS).....	12
Emergency Response.....	13
<b>Chapter 2: About SDS.....</b>	<b>14</b>
Introduction to SDS.....	15
SDS functionality.....	15
System Architecture.....	16
SDS Components.....	17
Distributed configuration.....	18
Centralized configuration.....	18
<b>Chapter 3: Configuration.....</b>	<b>22</b>
Options configuration.....	23
Options configuration elements.....	23
Editing options.....	30
DRMP configuration.....	31
DRMP configuration elements.....	31
Adding DRMP attributes.....	33
Editing DRMP attributes.....	33
Deleting DRMP connections.....	34
Connections configuration.....	34
Connections configuration elements.....	34
Viewing connections.....	36
Adding connections.....	37

Editing connections.....	37
Deleting connections.....	38
NAI hosts configuration.....	38
NAI hosts configuration elements.....	38
Viewing NAI hosts.....	39
Adding NAI hosts.....	39
Deleting NAI hosts.....	40
Destinations configuration.....	40
Destinations configuration elements.....	40
Viewing destinations.....	41
Adding destinations.....	42
Editing destinations.....	42
Deleting destinations.....	43
Destination Map configuration.....	43
Destination Map configuration elements.....	43
Viewing destination map connections.....	44
Adding destination maps.....	45
Editing destination maps.....	45
Deleting destination maps.....	46
Routing entities configuration.....	46
Routing entities configuration elements.....	47
Retrieving routing entities.....	48
Adding routing entities.....	49
Editing routing entities.....	49
Deleting routing entities.....	50
Subscribers.....	51
Subscribers elements.....	51
Retrieving subscribers.....	53
Adding subscribers.....	53
Editing subscribers.....	54
Deleting subscribers.....	55
Blacklist.....	55
Blacklist configuration elements.....	56
Retrieving blacklist values.....	56
Adding blacklist values.....	56
Deleting blacklist values.....	57
<b>Chapter 4: Maintenance.....</b>	<b>58</b>
Connections maintenance.....	60
Connections maintenance elements.....	60

Viewing connections status.....	61
Command log maintenance.....	62
Command log maintenance elements.....	63
Viewing maintenance command logs history.....	63
Exporting maintenance command logs.....	64
Relay exception log.....	65
Relay Exception Log maintenance elements.....	65
Viewing relay exception logs history.....	65
Import status maintenance.....	66
Import status maintenance elements.....	67
Viewing import status files.....	67
Export schedule and status maintenance.....	68
Export Schedule.....	69
Export Status.....	73
Remote audit.....	75
Remote audit elements.....	76
Viewing the status of a remote audit.....	78
Requesting a remote audit.....	78
Query .....	79
Query elements.....	79
Running a query (MSISDN, IMSI, MSISDN Prefix, IMSI Prefix, MSISDN Blacklist, IMSI Blacklist).....	81
Running a query (NAI User).....	82
Running a query (Wildcard NAI User, NAI Host, Destination, Counts, Counts by Destination, or DB Level).....	82
NPA Splits maintenance.....	83
NPA Splits elements.....	83
Viewing NPA Splits.....	84
Creating an NPA Split.....	84
Editing an NPA Split.....	85
Deleting an NPA Split.....	85
<b>Glossary.....</b>	<b>87</b>

# List of Figures

Figure 1: SDS System Diagram.....16

# List of Tables

Table 1: Admonishments.....11

Table 2: SDS Main Menu Options.....19

Table 3: Options Configuration Elements.....24

Table 4: DRMP Configuration Elements.....32

Table 5: Connections Configuration Elements.....35

Table 6: Connections Status Filtering Operators.....35

Table 7: Connections Status Filtering Categories.....36

Table 8: Connections Status Filtering Operators.....36

Table 9: NAI Hosts Configuration Elements.....38

Table 10: Connections Status Filtering Operators.....39

Table 11: Destinations Configuration Elements.....40

Table 12: Connections Status Filtering Operators.....41

Table 13: Destination Map Elements.....44

Table 14: Destination Map Filtering Categories.....44

Table 15: Connections Status Filtering Operators.....44

Table 16: Routing Entities Configuration Elements.....47

Table 17: Subscribers Elements.....52

Table 18: Blacklist Configuration Elements.....56

Table 19: Connections Maintenance Elements.....60

Table 20: Connections Status Filtering Operators.....61

Table 21: Command Log Maintenance Elements.....63

Table 22: Command Log Filtering Operators.....63

Table 23: Exporting Command Log Filtering Operators.....	64
Table 24: Exception Log Maintenance Elements.....	65
Table 25: Relay Exception Log Filtering Operators.....	66
Table 26: Import Status Maintenance Elements.....	67
Table 27: Connection Status Filtering Operators.....	68
Table 28: Interfaces for Subscriber Data Types.....	69
Table 29: Export Schedule Maintenance Elements.....	70
Table 30: Export Schedule Filtering Operators.....	70
Table 31: Export Data Types.....	71
Table 32: Export Data Types.....	72
Table 33: Export Status Maintenance Elements.....	74
Table 34: Export Status Filtering Operators.....	75
Table 35: Remote Audit Elements.....	76
Table 36: Remote Audit Filtering Operators.....	78
Table 37: Query Entry Elements.....	79
Table 38: Query Results Elements.....	80
Table 39: NPA Splits Maintenance Elements.....	83

# Chapter 1

## Introduction

---

### Topics:

- *Revision History.....10*
- *The SDS Help System.....10*
- *Scope and Audience.....10*
- *Manual organization.....10*
- *Documentation Admonishments.....11*
- *Related Publications.....11*
- *Locate Product Documentation on the Oracle Help Center Site.....11*
- *Customer Training.....12*
- *My Oracle Support (MOS).....12*
- *Emergency Response.....13*

*Introduction* provides a content overview of this guide with a brief summary about incidents, notifications, and the ID ranges for alarms and events. It also includes contact information and how to locate product documentation on the Customer Support site.

## Revision History

Date	Description
January 2017	Accessibility changes throughout.
September 2016	Updated Connections System ID parameter limit
September 2016	Provisioning Log Export added as a new maintenance feature

## The SDS Help System

Subscriber Database Server (SDS) provides the central provisioning of the Full-Address Based Resolution (FABR) data. The SDS, which is deployed geo-redundantly at a Primary and Disaster recovery site, connects with the Query server and the Data Processor Site Operation Administration and Maintenance (DP SOAM) servers at each diameter routing site or a standalone DP site to replicate and recover provisioned data to the associated components.

The Getting Started section of the Help provides an overview of the SDS and a description of how to use the Help. In this section you can find information about SDS including a product overview, the system architecture, and functions. Additionally, the Getting Started section familiarizes you with common GUI features including user interface elements, main menu options, supported browsers, and common user interface widgets.

## Scope and Audience

This guide is intended for trained and qualified system operators and administrators who are responsible for managing an SDS system.

## Manual organization

This document is organized into the following chapters:

- [Introduction](#) contains general information about the Diameter and Mediation help documentation, the organization of this manual, and how to get technical assistance.
- [About SDS](#) contains general information about the SDS documentation, the organization of this manual, and how to get technical assistance.
- [Configuration](#) describes the SDS Configuration menus options and their associated functions.
- [Maintenance](#) describes the SDS Maintenance menu options and their associated functions.

## Documentation Admonishments

Admonishments are icons and text throughout this manual that alert the reader to assure personal safety, to minimize possible service interruptions, and to warn of the potential for equipment damage.

**Table 1: Admonishments**

Icon	Description
 DANGER	Danger: (This icon and text indicate the possibility of <i>personal injury</i> .)
 WARNING	Warning: (This icon and text indicate the possibility of <i>equipment damage</i> .)
 CAUTION	Caution: (This icon and text indicate the possibility of <i>service interruption</i> .)
 TOPPLE	Topple: (This icon and text indicate the possibility of <i>personal injury and equipment damage</i> .)

## Related Publications

For information about additional publications related to this document, refer to the Oracle Help Center site. See [Locate Product Documentation on the Oracle Help Center Site](#) for more information on related product publications.

## Locate Product Documentation on the Oracle Help Center Site

Oracle Communications customer documentation is available on the web at the Oracle Help Center (OHC) site, <http://docs.oracle.com>. You do not have to register to access these documents. Viewing these files requires Adobe Acrobat Reader, which can be downloaded at <http://www.adobe.com>.

1. Access the Oracle Help Center site at <http://docs.oracle.com>.
2. Click **Industries**.

3. Under the Oracle Communications subheading, click the **Oracle Communications documentation** link.  
The Communications Documentation page appears. Most products covered by these documentation sets will appear under the headings “Network Session Delivery and Control Infrastructure” or “Platforms.”
4. Click on your Product and then the Release Number.  
A list of the entire documentation set for the selected product and release appears.
5. To download a file to your location, right-click the **PDF** link, select **Save target as** (or similar command based on your browser), and save to a local folder.

## Customer Training

Oracle University offers training for service providers and enterprises. Visit our web site to view, and register for, Oracle Communications training:

<http://education.oracle.com/communication>

To obtain contact phone numbers for countries or regions, visit the Oracle University Education web site:

[www.oracle.com/education/contacts](http://www.oracle.com/education/contacts)

## My Oracle Support (MOS)

MOS (<https://support.oracle.com>) is your initial point of contact for all product support and training needs. A representative at Customer Access Support (CAS) can assist you with MOS registration.

Call the CAS main number at 1-800-223-1711 (toll-free in the US), or call the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. When calling, make the selections in the sequence shown below on the Support telephone menu:

1. Select **2** for New Service Request
2. Select **3** for Hardware, Networking and Solaris Operating System Support
3. Select one of the following options:
  - For Technical issues such as creating a new Service Request (SR), Select **1**
  - For Non-technical issues such as registration or assistance with MOS, Select **2**

You will be connected to a live agent who can assist you with MOS registration and opening a support ticket.

MOS is available 24 hours a day, 7 days a week, 365 days a year.

## Emergency Response

In the event of a critical service situation, emergency response is offered by the Customer Access Support (CAS) main number at 1-800-223-1711 (toll-free in the US), or by calling the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. The emergency response provides immediate coverage, automatic escalation, and other features to ensure that the critical situation is resolved as rapidly as possible.

A critical situation is defined as a problem with the installed equipment that severely affects service, traffic, or maintenance capabilities, and requires immediate corrective action. Critical situations affect service and/or system operation resulting in one or several of these situations:

- A total system failure that results in loss of all transaction processing capability
- Significant reduction in system capacity or traffic handling capability
- Loss of the system's ability to perform automatic system reconfiguration
- Inability to restart a processor or the system
- Corruption of system databases that requires service affecting corrective actions
- Loss of access for maintenance or recovery operations
- Loss of the system ability to provide any required critical or major trouble notification

Any other problem severely affecting service, capacity/traffic, billing, and maintenance capabilities may be defined as critical by prior discussion and agreement with Oracle.

### Topics:

- [Introduction to SDS.....15](#)
- [System Architecture.....16](#)
- [Distributed configuration.....18](#)

This section of documentation describes the SDS application, its GUI, the system architecture, and centralized configuration.

Subscriber Database Server (SDS) provides the central provisioning of the Full-Address Based Resolution (FABR) data. The SDS, which is deployed geo-redundantly at a Primary and Disaster Recovery site, connects with the Query server and the Data Processor Site Operation Administration and Maintenance (DP SOAM) servers at each diameter routing site or a standalone DP site to replicate and recover provisioned data to the associated components.

## Introduction to SDS

The SDS/DP system consists of a Primary Provisioning Site, a Disaster Recovery (DR) Provisioning Site, and up to 32 Signaling Site servers with redundant DP SOAM servers and up to 10 DP servers in each site. Each Provisioning Site has an active/standby pair of servers in a high availability (HA) configuration and an optional third server configured as a Query server.

The SDS/DP system is built upon the EAGLE XG Platform. This platform provides a variety of services such as site-based GUI, HA capabilities (active/standby switchover and DR switchover), and database functionality (replication, backup, restore).

Every server within the SDS/DP system collects measurements, alarms, and events data. Every server has the ability to send traps directly to the customer's SNMP Manager and can collect measurement data. This measurement data is merged up in reverse direction of replication. The DP measurements are sent to the Active DP SOAM server, which sends the measurements from all DP servers and itself to the Primary Provisioning Site's Active SDS.

This introduction will familiarize you with the basic operation, features, and components of SDS.

## SDS functionality

Subscriber Database Server (SDS) provides the central provisioning of the Full-Address Based Resolution (FABR) data. The SDS, which is deployed geo-redundantly at a Primary and Disaster recovery site, connects with the Query Server and the Data Processor Site Operation Administration and Maintenance (DP SOAM) servers at each Diameter Signaling Router (DSR) site or a standalone DP site to replicate and recover provisioned data to the associated components.

SDS provides the following functionality:

- SDS Database – Stores subscriber data needed by the FABR application
- GUI-based provisioning
- Control the Diameter Internet Engineering Task Force (IETF) specification called Diameter Routing Message Priority (DRMP) to establish relative message priorities
- Enhanced Subscriber Table add functionality
- Support SOAP over HTTP and XML over TCP as provisioning interfaces
- SQL Interface – At query server for query only
- CSV and/or XML-formatted export and import of database contents
- Real Time replication to:
  - Local standby server at Primary site
  - Local query server at Primary site
  - Each server at Disaster Recovery site
  - Each DP SOAM and DP at up to 32 sites
- DP - DB Processor – A server that has a replica of the SDS database and is available for query by FABR applications
- Automatic scheduled NPA Split processing
- Provisioning Measurements and KPIs
- Alarms, Events and Logs for all interfaces

- DB Audit - Replication audit within replicas and Active SDS, and remote audit between SDS and HLR Router
- Query server
- Backup and Restore of SDS database components
- Disaster Recovery SDS – Geo-diverse site
- Automated Performance Data Export (APDE)
- Manage and associate routing destinations for routing entities that represent Subscriber identities
- Monitor exceptions
- Subscriber identity grouping
- Blacklist support
- Address resolution – Full address, as well as prefix address support

## System Architecture

SDS consists of an active/standby pair of SDS servers in an HA configuration, a third SDS server configured as a Query server, an optional DR SDS, redundant DP SOAM servers, and up to 10 DPs (Database Processor) servers. An SDS can have up to 32 sites, each capable of supporting up to 512 remote signaling points.

This figure provides an overview of the SDS architecture.




Figure 1: SDS System Diagram

## SDS Components

### SDS

The SDS has one active and one standby server running the SDS application and operating in a high availability configuration. It accepts subscriber data provisioned by the customer over SOAP or XML and replicates it to the DR SDS, the Query server, and all underlying servers. It also provides a GUI, which is used for configuration, user administration, and viewing alarms and measurements.

SDS distributes all successful incoming subscriber provisioning data, independent of source, to all downstream Network Elements (NEs) and to the DR SDS at a rate of up to 200 provisioning database updates per second. To ensure the database levels of the NEs are less than the database levels of the SDS and DR SDS, the active provisioning site SDS provisions the DR SDS before updating the NEs.

### DR SDS

The DR SDS is a geographically independent SDS component. The DR SDS has the same hardware configuration and network accessibility as the primary SDS.

The DR SDS's databases are kept updated through real-time replication of subscriber and application data from the active primary SDS. Under normal operating conditions, the DR SDS does not provision any downstream systems, but if made active, it will take over all the functions of the active SDS including the provisioning and database replication to underlying DP SOAMs.

### DP SOAM

The DP SOAM is the combination of an active and a standby application server running the DP SOAM application and operating in a high availability configuration. It accepts subscriber data replicated from the active primary SDS and in turn replicates it to all underlying DPs located in the same physical site. DP SOAM also provides a GUI used for viewing alarms and measurements details specific to components located within the site (DP SOAM, DP).

The DP SOAM supports up to 10 DPs.

### Query Server

The Query server is an independent application server containing a replicated version of the provisioning database. It accepts replicated subscriber data from the active primary SDS and stores it in a customer accessible SQL interface. A Query server is located in the same physical site as each SDS component (SDS/DR SDS).

### Network Element

NEs are containers that group and create relationships between servers in the network. There are two types of NEs:

- SDS: such as the SDS and the DR SDS
- DP SOAM: contains a pair of DP SOAM servers and one or more DP servers

The system can support two SDS NEs and up to 32 DP SOAM NEs.

## DPs

The Data Processors (DPs) are servers with the SDS application installed that are configured for DP functionality. They accept replicated subscriber data from the local DP SOAM and store it in a subscriber database.

The DPs are used for processing queries from the Message Processor (MP) for destination address resolution. DP receives database queries that include user identities such as MSISDN, IMSI, or URI and destination types and return the resolved destination's address FQDN and/or realm values.

Each Signaling Site can support multiple DP servers deployed at a single site to scale query capacity (by increments of 140,000 QPS per DP). Each Signaling Site can support up to 10 DPs.

The DP servers all contain a copy of the same SDS data. They are configured in an active/active mode. The MP is responsible for load-balancing requests across DP servers.

## Distributed configuration

The SDS supports centralized configurations where:

- All subscriber data configuration and maintenance occurs at the SDS level, and
- Application management, such as configuring servers, occurs at the SDS level.

Due to distributed configuration:

- All OAM Administration, Configuration, and Status & Manage tasks can only be performed when you are logged into an active primary SDS.
- SDS tasks related to the subscriber database are only available when logged into an active primary SDS, with the exception of querying the database.
- All Alarms, KPIs, Measurements, and Events are accessible from the SDS.

## Centralized configuration

System configuration and subscriber data is provisioned at the active server of the Primary SDS cluster, replicated to all other SDS, and then replicated to the active DP SOAM of each Network Element.

## SOAP/XML

The main method of subscriber data provisioning is SOAP or XML Interfaces. They allow one or several independent information systems supplied and maintained by the network operator to be used for provisioning databases and for configuring systems. Through the SOAP/XML interfaces, independent information systems may add, delete, change or retrieve information about any Routing Entities.

## GUI Provisioning

Local provisioning can be done using the SDS GUI. The GUI can be used to manage Provisioning setup, to make direct changes to the subscriber database entries, and to perform application operations, management, and provisioning.

This table shows the GUI options available when logged into an SDS.

Table 2: SDS Main Menu Options

Menu Item	Function
Administration	All options available: <ul style="list-style-type: none"> <li>• General Options</li> <li>• Access Control                             <ul style="list-style-type: none"> <li>• Users</li> <li>• Groups</li> <li>• Sessions</li> <li>• Certificate Management</li> <li>• Authorized IPs</li> <li>• SFTP Users</li> </ul> </li> <li>• Software Management                             <ul style="list-style-type: none"> <li>• Versions</li> <li>• Upgrade</li> </ul> </li> <li>• Remote Servers                             <ul style="list-style-type: none"> <li>• LDAP Authentication</li> <li>• SNMP Trapping</li> <li>• Data Export</li> <li>• DNS Configuration</li> </ul> </li> </ul>
Configuration	All options available: <ul style="list-style-type: none"> <li>• Network Elements</li> <li>• Network                             <ul style="list-style-type: none"> <li>• Devices</li> <li>• Routes</li> </ul> </li> <li>• Services</li> <li>• Servers</li> <li>• Server Groups</li> <li>• Resource Domains</li> <li>• Places</li> <li>• Place Associations</li> <li>• DSCP                             <ul style="list-style-type: none"> <li>• Interface DSCP</li> <li>• Port DSCP</li> </ul> </li> </ul>
Alarms & Events	All options available: <ul style="list-style-type: none"> <li>• View Active</li> <li>• View History</li> <li>• View Trap Log</li> </ul>

Menu Item	Function
Security Log	All options available: <ul style="list-style-type: none"> <li>• View History</li> </ul>
Status & Manage	All options available: <ul style="list-style-type: none"> <li>• Network Elements</li> <li>• Server</li> <li>• HA</li> <li>• Database</li> <li>• KPIs</li> <li>• Processes</li> <li>• Tasks                             <ul style="list-style-type: none"> <li>• Active Tasks</li> <li>• Scheduled Tasks</li> </ul> </li> <li>• Files</li> </ul>
Measurements	All options available: <ul style="list-style-type: none"> <li>• Report</li> </ul>
Communication Agent	All options available: <ul style="list-style-type: none"> <li>• Configuration                             <ul style="list-style-type: none"> <li>• Remote Servers</li> <li>• Connection Groups</li> <li>• Routed Services</li> </ul> </li> <li>• Maintenance                             <ul style="list-style-type: none"> <li>• Connection Status</li> <li>• Routed Services Status</li> <li>• HA Services Status</li> </ul> </li> </ul>
SDS	All options available: <ul style="list-style-type: none"> <li>• Configuration                             <ul style="list-style-type: none"> <li>• Options</li> <li>• DRMP</li> <li>• Connections</li> <li>• NAI Hosts</li> <li>• Destinations</li> <li>• Destination Map</li> <li>• Routing Entities</li> <li>• Subscribers</li> <li>• Blacklist</li> </ul> </li> <li>• Maintenance</li> </ul>

Menu Item	Function
	<ul style="list-style-type: none"> <li>• Connections</li> <li>• Command Log</li> <li>• Relay Exception Log</li> <li>• Import Status</li> <li>• Export Schedule</li> <li>• Export Status</li> <li>• Remote Audit</li> <li>• Query</li> <li>• NPA Splits</li> </ul>

# Chapter 3

## Configuration

---

### Topics:

- [Options configuration.....23](#)
- [DRMP configuration.....31](#)
- [Connections configuration.....34](#)
- [NAI hosts configuration.....38](#)
- [Destinations configuration.....40](#)
- [Destination Map configuration.....43](#)
- [Routing entities configuration.....46](#)
- [Subscribers.....51](#)
- [Blacklist.....55](#)

The **SDS Configuration** menu options allow you to configure provisioning options and view, insert, edit, and delete provisioning connections, NAI hosts, destinations, and routing entities.

The available database menu options will vary based on the type of server you are logged into and the permissions assigned to your group. If you do not see a menu option you need, make sure you are logged into the appropriate type of server and ask your administrator to make sure the group your user ID belongs to has the appropriate permissions.

## Options configuration

The **Options** page allows you to control how the mechanized interface works and controls features such as Import and Export.

### Provisioning options

Connections between the application and the provisioning client are set up using the **Connections** page (for more information, see [Connections configuration](#)). The **Options** page allows you to manage configuration options for these connections. Use this page to configure:

- Whether to allow connections and the maximum number of connections allowed
- Number of seconds of inactivity allowed before an idle connection is timed out
- Whether to allow log provisioning messages
- Number of seconds allowed between a transaction being committed and becoming durable
- TCP listening ports
- Whether to allow to importing from and exporting to a Remote Host

### Import options

The status of provisioning imports can be viewed using the **SDS Maintenance Import** page. For more information, see [Import status maintenance](#). Provisioning imports from a remote host are configured through the **SDS Configuration Options** page. Use this page to configure:

- Whether provisioning imports are enabled
- Remote host information, including the IP address, username, password, and import directory name
- Whether the import mode is blocking or non-blocking

### Export options

Provisioning exports are scheduled through the **SDS Configuration Export** page and the export status can be viewed through the **SDS Maintenance Export Status** page. For more information about this see [Import status maintenance](#). Use the **SDS Configuration Options** page to configure:

- Whether or not exports are allowed to be copied from this server to the remote host
- Remote host information, including the IP address, username, password, and export directory name
- Whether the export mode is blocking or non-blocking

**Note:** Command logs can be exported to a server other than the single remote server supported by APDE; **Log Provisioning Messages** must be enabled on the NO. Use the **SDS > Maintenance > Command Log** page to export logs.

## Options configuration elements

This table describes the fields on the **SDS Configuration Options** page.

**Table 3: Options Configuration Elements**

Element	Description	Data Input Notes
Allow Connections	If checked, incoming provisioning connections are allowed.	Format: Check box Range: Checked, Unchecked Default: Checked
Max Transaction Size	The maximum number of database manipulation commands per transaction.	Format: Digits only Range: 1–100 Default: 50
Log Provisioning Messages	If checked, all incoming and outgoing provisioning messages will be logged in the command log.  <b>Note:</b> Command logs can be exported to a server other than the single remote server supported by APDE.	Format: Check box Range: Checked, Unchecked Default: Checked
Transaction Durability Timeout	The number of seconds allowed between a transaction being committed and it becoming durable. If Transaction Durability Timeout lapses, DURABILITY_TIMEOUT (1024) response is sent to the originating client. The associated request should be resent to ensure the request was committed.	Format: Digits only; seconds Range: 2–3600 Default: 5
Remote Import Enabled	If checked, import files are imported from a remote host.	Format: Check box Range: Checked, Unchecked Default: Unchecked
Remote Import Mode	If set to <b>Non-Blocking</b> , updates are allowed on all provisioning connections while the remote import operation is in progress.  If set to <b>Blocking</b> , updates are not allowed.	Format: Pulldown menu Range: Non-Blocking, Blocking Default: Non-Blocking
Remote Import Host IP Address	The IP address of remote import host periodically queried for import files.	Format: Alphanumeric Range: 0–39 characters Range: Either an IPv4 or an IPv6 IP address.  IPv4 addresses are 32 bits, represented in a dot-decimal

Element	Description	Data Input Notes
		<p>notation like this: x.x.x.x where each x (called an octet) is a decimal value from 0 to 255. They are separated by periods. For example: 1.2.3.4 and 192.168.1.100 are valid IPv4 addresses.</p> <p>IPv6 addresses are 128 bits, represented in a colon-hexadecimal notation like this: z:z:z:z:z:z:z:z where each z is a group of hexadecimal digits ranging from 0 to ffff. They are separated by colons. Leading zeros may be omitted in each group. "::" can be used (at most once) in an IPv6 address to represent a range of as many zero fields as needed to populate the address to eight fields. So the IPv6 address 2001:db8:c18:1:260:3eff:fe47:1530 can also be represented as 2001:0db8:0c18:0001:0260:3eff:fe47:1530 and the IPv6 address ::1 is the same as 0000:0000:0000:0000:0000:0000:0000:0001</p>
Remote Import User	The Username for remote import host user.	Format: Alphanumeric Range: 0–255 characters
Remote Import Password	The password to exchange ssh keys with the remote import host. The password is cleared from this table after the keys have been exchanged.	Format: Alphanumeric Range: 0–255 characters
Remote Import Directory	The directory where import files exist on the remote import host.	Format: Alphanumeric Range: 0–255 characters
Export Mode	<p>If set to <b>Non-Blocking</b>, updates are allowed on all provisioning connections while the export operation is in progress.</p> <p>If set to <b>Blocking</b>, updates are not allowed.</p>	Format: Pulldown menu Range: Non-Blocking, Blocking Default: Non-Blocking
Remote Export Transfers Enabled	If checked, export files will be copied to the remote export host.	Format: Check box Range: Checked, Unchecked Default: Unchecked

Element	Description	Data Input Notes
Remote Export Host IP Address	The IP address of the remote export host to where export files may be configured automatically transferred.	<p>Format: Alphanumeric</p> <p>Range: 0–39 characters</p> <p>Range: Either an IPv4 or an IPv6 IP address.</p> <p>IPv4 addresses are 32 bits, represented in a dot-decimal notation like this: x.x.x.x where each x (called an octet) is a decimal value from 0 to 255. They are separated by periods. For example: 1.2.3.4 and 192.168.1.100 are valid IPv4 addresses.</p> <p>IPv6 addresses are 128 bits, represented in a colon-hexadecimal notation like this: z:z:z:z:z:z:z:z where each z is a group of hexadecimal digits ranging from 0 to ffff. They are separated by colons. Leading zeros may be omitted in each group. "::" can be used (at most once) in an IPv6 address to represent a range of as many zero fields as needed to populate the address to eight fields. So the IPv6 address 2001:db8:c18:1:260:3eff:fe47:1530 can also be represented as 2001:0db8:0c18:0001:0260:3eff:fe47:1530 and the IPv6 address ::1 is the same as 0000:0000:0000:0000:0000:0000:0000:0001</p>
Remote Export User	The username for remote export host user.	<p>Format: Alphanumeric</p> <p>Range: 0–255 characters</p>
Remote Export Password	The Password to exchange ssh keys with the remote export host. The password is cleared from this table after the keys have been exchanged.	<p>Format: Alphanumeric</p> <p>Range: 0–255 characters</p>
Remote Export Directory	The directory in the Remote Export Host to which export files are transferred if configured.	<p>Format: Alphanumeric</p> <p>Range: 0–255 characters</p>
Remote Audit Receive Window Size	The maximum number of retrieval messages that can be received and buffered by the Provisioning Database Application on the remote	<p>Format: Digits only</p> <p>Range: 5–2500</p> <p>Default: 500</p>

Element	Description	Data Input Notes
	system. After this amount is reached, no more messages will be sent until acknowledgments are received from the remote system.	
Remote Audit Send Message Rate	The maximum rate of messages/second in which retrieval messages will be sent to the Provisioning Database Application on the remote systems.	Format: Digits only Range: 5–2500 Default: 500
Remote Audit Number Range Limit	The maximum number of records that can be queried per request message.	Format: Digits only Range: 100–100000 Default: 1000
PDB Relay Enabled	Whether or not to relay successful incoming provisioning requests to a Provisioning Database Application on a remote system.  <b>Note:</b> This feature requires that the Log Provisioning Messages option is enabled.	Format: Check box Range: Checked, Unchecked Default: Unchecked
PDB Relay Primary Remote System VIP Address	The VIP address of the primary remote system of the Provisioning Database Application that is running.  <b>Note:</b> Changes to the VIP address listening port do not take affect until PDB Relay is restarted.	Format: Alphanumeric Range: 0–39 characters Range: Either an IPv4 or an IPv6 IP address.  IPv4 addresses are 32 bits, represented in a dot-decimal notation like this: x.x.x.x where each x (called an octet) is a decimal value from 0 to 255. They are separated by periods. For example: 1.2.3.4 and 192.168.1.100 are valid IPv4 addresses.  IPv6 addresses are 128 bits, represented in a colon-hexadecimal notation like this: z:z:z:z:z:z:z:z where each z is a group of hexadecimal digits ranging from 0 to ffff. They are separated by colons. Leading zeros may be omitted in each group. "::" can be used (at most once) in an IPv6 address to represent a range of as many zero fields as needed to populate the address to eight fields. So the IPv6 address

Element	Description	Data Input Notes
		2001:db8:c18:1:260:3eff:fe47:1530 can also be represented as 2001:0db8:0c18:0001:0260:3eff:fe47:1530 and the IPv6 address ::1 is the same as 0000:0000:0000:0000:0000:0000:0000:0001
PDB Relay Disaster Recovery Remote System VIP Address	The VIP address of the Disaster Recovery remote system on which the Provisioning Database Application is running.  <b>Note:</b> Changes to the VIP address do not take affect until PDB Relay is restarted.	Format: Alphanumeric Range: 0–39 characters IPv4 addresses are 32 bits, represented in a dot-decimal notation like this: x.x.x.x where each x (called an octet) is a decimal value from 0 to 255. They are separated by periods. For example: 1.2.3.4 and 192.168.1.100 are valid IPv4 addresses.  IPv6 addresses are 128 bits, represented in a colon-hexadecimal notation like this: z:z:z:z:z:z:z:z where each z is a group of hexadecimal digits ranging from 0 to ffff. They are separated by colons. Leading zeros may be omitted in each group. "::" can be used (at most once) in an IPv6 address to represent a range of as many zero fields as needed to populate the address to eight fields. So the IPv6 address 2001:db8:c18:1:260:3eff:fe47:1530 can also be represented as 2001:0db8:0c18:0001:0260:3eff:fe47:1530 and the IPv6 address ::1 is the same as 0000:0000:0000:0000:0000:0000:0000:0001
PDB Relay Remote System Port	The TCP listening port of the Provisioning Database Application on the remote system.  <b>Note:</b> Changes to the TCP listening port do not take affect until PDB Relay is restarted.	Format: Digits only Range: 0–65535 Default: 5873
PDB Relay Receive Window Size	The maximum number of provisioning commands that can be received and buffered by the	Format: Digits only Range: 5–2500

Element	Description	Data Input Notes
	Provisioning Database Application on the remote system. After this amount is reached, no more commands will be sent until acknowledgments are received from the remote system.	Default: 500
PDB Relay Send Command Rate	The maximum rate (in commands/second) in which commands will be relayed/sent to the Provisioning Database Application on remote system.	Format: Digits only Range: 5–2500 Default: 500
PDB Relay Timestamp (read-only)	The timestamp of the last provisioning message relayed to the Provisioning Database Application on the remote system.	Format: Read-only timestamp
XML Interface Port	XML interface TCP (unsecured) listening port.  To disable this port, set it to 0.  <b>Note:</b> Changes to the TCP listening port do not take effect until the xds process is restarted. You must also specify a different port other than the SOAP interface.	Format: Digits only Range: 0–65535 Default: 5875
XML Interface Idle Timeout	The maximum number of seconds an open connection remains active without a request being sent before the connection is dropped.	Format: Digits only; seconds Range: 1–86400 Default: 1200
Maximum XML Connections	The maximum number of simultaneous XML interface client connections.  <b>Note:</b> Changes to the Maximum XML Connections option do not take effect until the xds process is restarted.	Format: Digits only Range: 1–120 Default: 120
SOAP Interface Port	The SOAP interface TCP listening port.  To disable this port, set it to 0.  <b>Note:</b> Changes to the TCP listening port do not take effect until the xds process is restarted. You must also specify a different port other than the XML interface.	Format: Digits only Range: 0–65535 Default: 5876

Element	Description	Data Input Notes
SOAP Interface Idle Timeout	The maximum time (in seconds) an open connection remains active without a request being sent, before the connection is dropped.	Format: Digits only Range = 1-86400 Default = 1200
Maximum SOAP Connections	The maximum number of simultaneous SOAP interface client connections.  <b>Note:</b> Changes to the Maximum SOAP Connections option do not take effect until the xds process is restarted.	Format: Digits only Range: 1-120 Default: 120
SOAP Secure Mode	If set to <b>Secure</b> , the SOAP interface operates in secure mode (using TSL).  <b>Note:</b> Changes to the SOAP Secure Mode option do not take effect until the xds process is restarted.	Format: Pulldown menu Range: Secure, Unsecure Default: Unsecure
Maximum Transaction Lifetime	The maximum number of seconds a transaction remains open before automatically being rolled back if a commit or rollback is not performed.  To disable this timeout, set it to <b>0</b> .	Format: Digits only; seconds Range: 0-3600 Default: 60
Maintain Subscriber Timestamp (read-only)	Whether or not to maintain subscriber creation and last updated timestamp.  <b>Note:</b> Changes to this option do not take effect until the application processes are restarted.	Format: Check box Range: Checked, Unchecked Default: Unchecked

### Editing options

You can only perform this task when logged into the active SDS server.

1. Select **SDS > Configuration > Options**.

The **SDS Configuration Options** page appears.

2. Modify the options you want to change by entering information in the appropriate fields.

For a detailed explanation about the options and valid input for these fields, see [Options configuration elements](#).

3. Click **Apply**.

If field validations succeed, the changes are saved and you remain on the same page. A successful update message appears.

If the page contains any values that are not valid or are out of range, an error message appears.

## DRMP configuration

The **DRMP** page allows you to control the Diameter Internet Engineering Task Force (IETF) specification called Diameter Routing Message Priority (DRMP). DRMP allows Diameter nodes to embed the relative priority of the message into a Diameter message used for routing decisions, resource allocation, and overload abatement decisions. The priorities are based on a scale of 0 to 15, where priority value 0 is specified as the highest priority and priority value 15 is the lowest priority. DRMP performs congestion control and message throttling decisions based on DRMP-based relative priority of the Diameter message.

**Note:** DRMP Priority value of 0 is treated as highest Priority and 15 as lowest Priority, which is in reverse order of DSR Priority values.

When making routing and resource allocation decisions, Diameter nodes currently have no generic mechanism to determine the relative priority of Diameter messages. IETF DRMP addresses this by defining a mechanism to allow diameter endpoints to indicate the relative priority of Diameter transactions. With this information, Diameter nodes can factor that priority into routing, resource allocation, and overload abatement decisions. For example, this includes first responder related signaling, emergency call related signaling, differentiated services, Application specific priorities, and so on. This allows SDS to support a custom policer mode based on tracker/shaper algorithm for managing congestion for all internal congestion points.

The custom policer mode tracks the offered traffic to each congestion point and arranges them by priority and color segments and stacks it according to the Site MO Discard Policy:

- Discard by Priority Only
- Discard by Color within Priority
- Discard by Priority within Color

If any of the congestion point's (Task Queue, Task Thread Pool, and so on) congestion level is above normal, the custom policer discards a fixed percentage of messages depending on Discard Policy (of that site) starting from messages lowest in stacking order. The percentage of messages discarded are configured as:

- CL1 Discard %: 15%
- CL2 Discard %: 30%
- CL3 Discard %: 45%

For information about DRMP APV and IETF, see *Diameter User's Guide*.

## DRMP configuration elements

This table describes the fields on the **DRMP** page. You can perform this task when logged into an SDS or from the DP SOAM GUI. Use this page to view the DRMP Admin State and the priority values set for each SOAM Server group. For more information, see *Diameter User's Guide*.

Table 4: DRMP Configuration Elements

Element	Description	Data Input Notes
SOAM Server Group Name	The name of the server group.	Format: Alphanumeric Range: NA Default: NA
16 Priority Admin State	The server group administrative state; determines 16 or 4 message priorities support. <b>Note:</b> Application Restart is required.	Format: Textbox Range: Enabled (supports 16 internal message priorities [0-15]), Disabled (supports 4 internal message priorities [(0-3)]. Default: Disabled
NGN-PS Admin State	Defines whether the NGN-PS feature is enabled or not. <b>Note:</b> This parameter is disabled and non-editable when 16 Priority Admin State is disabled.	Format: Textbox Range: Enabled, Disabled Default: Disabled (the system does not provide NGN-PS treatment to any messages)
Minimum Inviolable Priority	Defines the minimum priority the system considers inviolable from a message priority treatment. A Stack Event with a priority greater than or equal to this attribute is not subject to congestion controls.	Format: Digits only Range: 3, 15, or 99 <ul style="list-style-type: none"> <li>• 3 - when 16 Priority Admin State is Disabled (irrespective of NGN-PS Admin State)</li> <li>• 15 - when 16 Priority and NGN-PS Admin State are Enabled</li> <li>• 99 - when 16 Priority Admin State is Enabled, but NGN-PS Admin State is Disabled</li> </ul> Default: 3
Minimum Response Priority	Defines the minimum priority the system assigns to ingress Diameter Answer message.	Format: Digits only Range: 0 or 2 <ul style="list-style-type: none"> <li>• 2 - when 16 Priority Admin State is Disabled</li> <li>• 0 - when 16 Priority Admin State is Enabled</li> </ul> Default: 2
Discard Policy	The order of priority and/or color-based traffic segments to consider when determining discard candidates for the application of	Format: Alpha Range: Priority Only, Priority Within Color, Color Within Priority

Element	Description	Data Input Notes
	treatment during SDS Congestion processing.	Default: Priority Only

### Adding DRMP attributes

You can only perform this task for the given SOAM Server Group.

1. Select **SDS > Configuration > DRMP**.  
The **DRMP** page appears.
2. Click **Insert**.  
The **SDS Configuration DRMP [Insert]** page appears.
3. Select a SOAM server group name in the **Server Group Name** pulldown menu.
4. Set the **16 Priority Admin State**.
5. Set the **NGN-PS Admin State**.
6. Set the **Minimum Inviolable Priority**.
  - Select 3 when 16 Priority Admin State is Disabled (irrespective of NGN-PS Admin State). This is the default.
  - Select 15 when 16 Priority and NGN-PS Admin State are Enabled.
  - Select 16 when Priority Admin State is Enabled but NGN-PS Admin State is Disabled.
7. Set the **Minimum Response Priority**. Select **0** or **2**.
8. Set the **Discard Priority**. Select **Priority Only**, **Priority Within Color**, **Color Within Priority**.
9. Perform one of the following:
  - Click **OK** to save the connection and return to the SDS configuration DRMP page.
  - Click **Apply** to save the connection and remain on this page.
  - Click **Cancel** to return to the **DRMP** page without saving the changes.

If field validations succeed, the connection is saved. If **OK** or **Apply** is clicked and any of the following conditions exist, an error message appears:

- Any required field is empty; no value was entered or selected
- The entry in any field is not valid (wrong data type or out of the valid range)

### Editing DRMP attributes

You can only perform this task for the given SOAM Server Group.

1. Select **SDS > Configuration > DRMP**.  
The **DRMP** page appears.
2. Click **Edit**.
3. Modify the attributes you want to change by entering information in the appropriate fields.  
For a detailed explanation about the options and valid input for these fields, see [DRMP configuration elements](#).
4. Click **OK**.

If field validations succeed, the changes are saved and you remain on the same page. A successful update message appears.

If the page contains any values that are not valid or are out of range, an error message appears.

## Deleting DRMP connections

You can only perform this task for the given SOAM Server Group.

1. Select **SDS > Configuration > DRMP**.  
The **DRMP** page appears.
2. Highlight the DRMP connection you want to delete and click **Delete**.  
A popup confirmation window appears.
3. Perform one of the following actions:
  - Click **OK** to delete the connection.
  - Click **Cancel** to cancel the delete function and return to the **DRMP** page.

## Connections configuration

The **Connections** page allows you to manage the configuration for servers permitted to establish a connection to the active Primary Provisioning Site's Active SDS server. Only the servers specified in the Connections list are allowed to remotely connect to the server and execute commands.

**Note:** The client host being associated with permissions must exist in the system before adding a subscribing client permission record.

SDS allows up to 120 simultaneous provisioning connections and supports secure and unsecure SOAP connections. While the application is capable of supporting 120 connections, the maximum number of connections allowed can be limited using the **Options** page. For more information about this option, see [Options configuration](#).

From the **Connections** page, you can:

- Filter the list of server to display only the desired servers.
- View the list of servers allowed to establish a remote connection and each server's permissions.
- Configure the SDS to allow connection requests from remote servers.
- Modify the System ID, IP address, and permissions for listed servers.
- Delete servers from the connections list.

## Connections configuration elements

This table describes the fields on the **SDS Configuration Connections** page.

**Table 5: Connections Configuration Elements**

Element	Description	Data Input Notes
Filter fields	Pulldown menu of available filters and additional fields to modify the search options	Format: Selectable list
System ID	Identification for the system	Format: Alphanumeric Range: 1– 255 characters
IP Address	IP address of the client that will connect to SDS	Format: Alphanumeric Range: Either an IPv4 or an IPv6 IP address  IPv4 addresses are 32 bits, represented in a dot-decimal notation like this: x.x.x.x where each x (called an octet) is a decimal value from 0 to 255. They are separated by periods. For example: 1.2.3.4 and 192.168.1.100 are valid IPv4 addresses.  IPv6 addresses are 128 bits, represented in a colon-hexadecimal notation like this: z:z:z:z:z:z:z:z where each z is a group of hexadecimal digits ranging from 0 to ffff. They are separated by colons. Leading zeros may be omitted in each group. "::" can be used (at most once) in an IPv6 address to represent a range of as many zero fields as needed to populate the address to eight fields. So the IPv6 address 2001:db8:c18:1:260:3eff:fe47:1530 can also be represented as 2001:0db8:0c18:0001:0260:3eff:fe47:1530 and the IPv6 address ::1 is the same as 0000:0000:0000:0000:0000:0000:0000:0001
Permission	Database permissions for this client	Format: Pulldown list Range: READ_ONLY, READ_WRITE Default: READ_ONLY

**Table 6: Connections Status Filtering Operators**

Operator	Description
=	Is equal to
!=	Is not equal to
>	Is greater than
>=	Is equal to or greater than
<	Is less than
<=	Is equal to or less than
Like	Is Like (wildcard is * character)

Operator	Description
Is Null	has no entry (is zero)

### Viewing connections

You can perform this task when logged into an SDS or from the DP SOAM GUI.

1. Select **SDS > Configuration > Connections**.  
The **SDS Configuration Connections** page appears with the currently allowed connections listed in the table. Click on any column heading to reorder the rows.
2. To look for a specific connection, click **Filter**.
3. Select NAI Host from the **Display Filter** pulldown list.
4. Select the category to perform the filtering.

**Table 7: Connections Status Filtering Categories**

Category	Description
System ID	Identifying text for the system
IP Address	IP address (either an IPv4 or IPv6) of the client that connects to SDS
Permission	Database permission group for the client

5. Choose the filtering operator.

**Table 8: Connections Status Filtering Operators**

Operator	Description
=	Is equal to
!=	Is not equal to
>	Is greater than
>=	Is equal to or greater than
<	Is less than
<=	Is equal to or less than
Like	Is Like (wildcard is * character)
Is Null	has no entry (is zero)

6. Enter the target character string to filter on in the text box.
7. Click **Go**.

## Adding connections

You can only perform this task when logged into the Active Primary SDS.

1. Select **SDS > Configuration > Connections**.  
The **SDS Configuration Connections** page appears.
2. Click **Insert**.  
The **SDS Configuration Connections [Insert]** page appears.
3. Enter a system ID in the **System ID** field.
4. Enter a unique IP address for the connection in the **IP Address** field.
5. Select the permissions level for the connection from the **Permissions** pulldown menu.
  - Select **READ\_ONLY** to grant read-only access for the client with this connection. This is the default.
  - Select **READ\_WRITE** to grant read and write access for the client with this connection.
6. Perform one of the following:
  - Click **OK** to save the connection and return to the SDS configuration connections page.
  - Click **Apply** to save the connection and remain on this page.
  - Click **Cancel** to return to the **SDS Configuration Connections** page without saving the changes.

If field validations succeed, the connection is saved. If **OK** or **Apply** is clicked and any of the following conditions exist, an error message appears:

- Any required field is empty; no value was entered or selected
- The entry in any field is not valid (wrong data type or out of the valid range)
- The IP Address is not unique; it already exists in the system

## Editing connections

You can only perform this task when logged into the Active Primary SDS.

1. Select **SDS > Configuration > Connections**.  
The **SDS Configuration Connections** page appears.
2. Highlight the connection you want to edit by clicking on the row and then click **Edit**.  
The **SDS Configuration Connections [Edit]** page appears.
3. Edit the System ID, IP Address, and/or Permission for the connection.  
For more information about these fields, see [Connections configuration elements](#).
4. Click **OK** to save the changes and return to the **SDS Configuration Connections** page.  
If field validations succeed, the connection is saved. If any of the following conditions exist, an error message appears:
  - If the entry in any field is not valid or are out of range
  - If a required field is empty (not entered)
  - If the IP Address is not unique

## Deleting connections

You can only perform this task when logged into the Active Primary SDS.

1. Select **SDS > Configuration > Connections**.  
The **SDS Configuration Connections** page appears.
2. Highlight the connection you want to delete and click **Delete**.  
A popup confirmation window appears.
3. Perform one of the following actions:
  - Click **OK** to delete the connection.
  - Click **Cancel** to cancel the delete function and return to the **SDS Configuration Connections** page.

## NAI hosts configuration

The **NAI Hosts** page allows you to manage the Network Access Identifier (NAI) host systems used for provisioning NAI User-associated routing entities.

From the **NAI Hosts** page, you can:

- Filter the list of hosts to display only the desired hosts.
- View the NAI Hosts configured for NAI User.
- Add a NAI Host.
- Delete a NAI Host.

## NAI hosts configuration elements

This table describes the fields on the SDS Configuration NAI Hosts page.

**Table 9: NAI Hosts Configuration Elements**

Element	Description	Data Input Notes
Filter fields	Pull-down menu of available filters and additional fields to modify the search options.	Format: Selectable list.
NAI Host	Network Access Identifier hostname	Format: alphanumeric (A-Z, a-z, 0-1) and special characters: period (.), hyphen (-), plus (+), underscore (_), At sign (@), dollar sign (\$), pound or number sign (#), forward slash (/), double quote ("), asterisk (*), exclamation point (!), and colon (:)  Range: 1–64 characters

## Viewing NAI hosts

You can perform this task when logged into an SDS or from the DP SOAM GUI.

1. Select **SDS > Configuration > NAI Hosts**.  
The **SDS Configuration NAI Hosts** page appears with the current NAI hosts are listed in the table. Click on any column heading to reorder the rows.
2. To look for a specific NAI Host, click **Filter**.
3. Select NAI Host from the **Display Filter** pulldown list.
4. Choose the filtering operator.

**Table 10: Connections Status Filtering Operators**

Operator	Description
=	Is equal to
!=	Is not equal to
>	Is greater than
>=	Is equal to or greater than
<	Is less than
<=	Is equal to or less than
Like	Is Like (wildcard is * character)
Is Null	has no entry (is zero)

5. Enter the NAI Host to filter on in the text box.
6. Click **Go**.

## Adding NAI hosts

You can only perform this task when logged into the Active Primary SDS.

1. Select **SDS > Configuration > NAI Hosts**.  
The **SDS Configuration NAI Hosts** page appears.
2. Click **Insert**.  
The **SDS Configuration NAI Hosts [Insert]** page appears.
3. Enter a unique hostname in the **NAI Host** field.
4. Perform one of the following:
  - Click **OK** to save the hostname and return to the SDS configuration **NAI Hosts** page.
  - Click **Apply** to save the hostname and remain on this page.
  - Click **Cancel** to return to the **SDS Configuration NAI Hosts** page without saving the changes.

If field validation succeeds, the host is saved. If **OK** or **Apply** is clicked and any of the following conditions exist, an error message appears:

- The required field is empty; no value was entered.

- The entry in the **NAI Host** field contains an invalid character.
- The hostname is not unique; it already exists in the system.

## Deleting NAI hosts

You can only perform this task when logged into the Active Primary SDS.

Before performing this task, disable and delete any association that may exist between the NAI host and routing entity (NAI User or Wildcard NAI User).

1. Select **SDS > Configuration > NAI Hosts**.  
The **SDS Configuration NAI Hosts** page appears.
2. Highlight the NAI host you want to delete and click **Delete**.  
A popup confirmation window appears.
3. Perform one of the following actions:
  - Click **OK** to delete the NAI Host.
  - Click **Cancel** to cancel the delete function and return to the **SDS Configuration NAI Hosts** page.

If **OK** is clicked and the following condition exists, an error message appears:

- The NAI Host is in use by a routing entity.

## Destinations configuration

The **Destinations** page allows you to manage routing destinations used by routing entities.

From the **SDS Configuration Destination** page, you can perform the following actions:

- Retrieve information for a specific Destination.
- Add a Destination.
- Update the information associated with an existing Destination.
- Delete a Destination.

## Destinations configuration elements

This table describes the fields on the SDS Configuration Destinations page.

**Table 11: Destinations Configuration Elements**

Element	Description	Data Input Notes
Filter fields	Pulldown menu of available filters and additional fields to modify the search options.	Format: Selectable list.

Element	Description	Data Input Notes
Name	Name of the destination	Format: Alphanumeric (A-Z, a-z, 0-1) and special characters: period (.), hyphen (-), plus (+), underscore (_), At sign (@), dollar sign (\$), pound or number sign (#), forward slash (/), double quote ("), asterisk (*), exclamation point (!), and colon (:) Range: 1-32 characters; cannot start with a digit and must contain at least one alpha character.
Type	Type of destination	Format: Pulldown list <ul style="list-style-type: none"> <li>• IMS HSS</li> <li>• LTE HSS</li> <li>• PCRF</li> <li>• OCF</li> <li>• OFCS</li> <li>• AAA</li> <li>• User defined 1</li> <li>• User defined 2</li> </ul>
FQDN	Unique fully qualified domain name	Format: String consisting of a list of labels separated by dots. A label might contain letters, digits, dash (-), and underscore (_). A label must begin with a letter or underscore, and must end with a letter or digit. Underscore can be used only as the first character. Range: 0-255 characters
Realm	Realm	Format: String consisting of a list of labels separated by dots. A label might contain letters, digits, dash (-), and underscore (_). A label must begin with a letter or underscore, and must end with a letter or digit. Underscore can be used only as the first character. Range: 0-255 characters

### Viewing destinations

You can perform this task when logged into an SDS or from the DP SOAM GUI.

1. Select **SDS > Configuration > Destinations**.  
The **SDS Configuration Destinations** page appears with the current destinations listed in the table.
2. To look for a specific Destination, click **Filter**.
3. Select Destination Name from the **Display Filter** pulldown list.
4. Choose the filtering operator.

**Table 12: Connections Status Filtering Operators**

Operator	Description
=	Is equal to

Operator	Description
!=	Is not equal to
>	Is greater than
>=	Is equal to or greater than
<	Is less than
<=	Is equal to or less than
Like	Is Like (wildcard is * character)
Is Null	has no entry (is zero)

5. Enter the Destination Name to filter on in the text box.
6. Click **Go**.

## Adding destinations

You can only perform this task when logged into the Active Primary SDS.

1. Select **SDS > Configuration > Destinations**.  
The **SDS Configuration Destinations** page appears.
  2. Click **Insert**.  
The **SDS Configuration Destinations [Insert]** page appears.
  3. Enter a unique name in the **Name** field.
  4. Select the type of destination from the **Type** pulldown list.
  5. Enter a fully-qualified domain name (FQDN) in the **FQDN** field.
  6. Enter the realm in the **Realm** field.
  7. Perform one of the following:
    - Click **OK** to save the connection and return to the SDS configuration connections page.
    - Click **Apply** to save the connection and remain on this page.
    - Click **Cancel** to return to the **SDS Configuration Destinations** page without saving the changes.
- If **OK** or **Apply** is clicked and any of the following conditions exist, an error message appears:
- Any required field is empty; no value was entered or selected
  - The entry in any field is not valid (wrong data type or out of the valid range)

## Editing destinations

You can only perform this task when logged into the Active Primary SDS.

1. Select **SDS > Configuration > Destinations**.  
The **SDS Configuration Destinations** page appears.
2. Highlight the destination you want to edit and click **Edit**.  
The **SDS Configuration Destinations [Edit]** page appears.
3. Edit the **FQDN** and/or **Realm** fields.

For more information about these fields, see [Destinations configuration elements](#).

**Note:** When updating a destination, you are permitted to leave both the **FQDN** and **Realm** empty. This action is permitted and the destination is retained despite having no data for these attributes.

4. Perform one of the following:
  - Click **OK** to save the changes to the destination and return to the **SDS Configuration Destinations** page.
  - Click **Cancel** to return to the **SDS Configuration Destinations** page without saving the changes.

## Deleting destinations

You can only perform this task when logged into the Active Primary SDS.

A Destination cannot be deleted while any routing entity, NAI/Wildcard User, or Destination remains associated with them. Before you perform this task, disable and delete any connections that use the Destination.

1. Select **SDS > Configuration > Destinations**.  
The **SDS Configuration Destinations** page appears.
2. Highlight the destination you want to delete and click **Delete**.  
A popup confirmation window appears.
3. Perform one of the following actions:
  - Click **OK** to delete the connection.
  - Click **Cancel** to cancel the delete function and return to the **SDS Configuration Destinations** page.

If **OK** is clicked and any of the following conditions exist, an error message appears:

- No updates were made to the database.
- Object currently in use; destination is used by a route.
- Object currently in use; destination is used by a destination map.

## Destination Map configuration

The **Destination map** page allows you to add, modify, or delete additional data on an existing Destination.

From the **Destination Map** page, you can associate a destination to a HLR Router Network entity.

## Destination Map configuration elements

This table describes elements on the **SDS Configuration Destination Map** page.

**Table 13: Destination Map Elements**

Element	Description	Data Input Notes
Filter fields	Pulldown menu of available filters and additional fields to modify the search options	Format: Selectable list
Destination	Destination field	Format: Alphanumeric Range: 1–32 characters
Network Entity	The E.164 address of a service node used by HLR Router	Format: Numeric Range: 8–15 characters

### Viewing destination map connections

Use this page to view the list of Destination Map entries.

1. Select **SDS > Configuration > Destination Map**.  
The **SDS Configuration Destination Map** page appears with the current destination maps listed in the destination map table. Click on any column heading to reorder the rows.
2. To look for a specific Destination Map, click **Filter**.
3. Select the category to perform the filtering.

**Table 14: Destination Map Filtering Categories**

Category	Description
Destination	Destination Name
Network Entity	The E.164 address of a service node used by the HLR router

4. Choose the filtering operator.

**Table 15: Connections Status Filtering Operators**

Operator	Description
=	Is equal to
!=	Is not equal to
>	Is greater than
>=	Is equal to or greater than
<	Is less than
<=	Is equal to or less than
Like	Is Like (wildcard is * character)
Is Null	has no entry (is zero)

5. Enter the Destination Name to filter on in the text box.
6. Click **Go**.

## Adding destination maps

Use this page to manually add a destination map to the database. An IMSSHSS Destination and Network Entity must be provided when adding a Destination Map entry. The Destination value must match a name of an existing Destination entry. The **OK** and **Apply** buttons are disabled until a character is entered into either the Destination or Network Entity field.

**Note:** You can only perform this task when logged into the Active Primary SDS.

1. Select **SDS > Configuration > Destination Map**.  
The **SDS Configuration Destination Map** page appears.
2. Click **Insert**.  
The **SDS Configuration Destination Map [Insert]** page appears.
3. Enter a Destination name in the **Destination** field. The name must match an IMSSHSS Destination name that has already been entered into the database.
4. Enter a E.164 address for the server node for the **Network Entity** in the Network Entity field.
5. Perform one of the following:
  - Click **OK** to save the destination map and return to the **Destinations Map** page.
  - Click **Apply** to save the destination map and remain on this page.
  - Click **Cancel** to return to the **SDS Configuration Destinations Map** page without saving the changes.

If field validations succeed, the destination map is saved. If **OK** or **Apply** is clicked and any of the following conditions exist, an error message appears:

- Missing required information in the **Destination** field.
- Missing required information in the **Network Entity** field.
- Invalid characters in the **Destination** field.
- Only digits are allowed in the **Network Entity** field.
- The **Network Entity** field must contain at least eight digits.
- Destination not found.
- The Destination's type must be IMS HSS to have a Destination Map entry.

## Editing destination maps

Use this page to manually change an existing destination map in the database. The **OK** button is disabled until a character is entered into either the Destination or Network Entity field.

You can only perform this task when logged into the Active Primary SDS.

**Note:** A service node must be provided when modifying a destination map.

1. Select **SDS > Configuration > Destination Map**.  
The **SDS Configuration Destination Map** page appears.
2. Highlight the Destination map you want to edit and click **Edit**.

The **SDS Configuration Destination Map [Edit]** page appears.

3. Edit the E.164 address for the server node in the **Network Entity** field.
4. Perform one of the following:
  - Click **OK** to save the destination map and return to the **Destination Map** page.
  - Click **Cancel** to return to the **SDS Configuration Destination Map** page without saving the changes.

If any of the following conditions exist, an error message appears:

- Missing required information in the **Network Entity** field.
- Only digits are allowed in the **Network Entity** field.
- The **Network Entity** field must contain eight digits.

## Deleting destination maps

This page allows you to manually delete a destination map from the database. A Destination Map cannot be deleted while any IMSI or MSISDN routing entities remain associated with the destination.

**Note:** You can only perform this task when logged into the Active Primary SDS.

1. Select **SDS > Configuration > Destination Map**.  
The **SDS Configuration Destination Map** page appears.
2. Highlight the Destination map you want to delete and click **Delete**.  
A popup confirmation window appears.
3. Perform one of the following actions:
  - Click **OK** to delete the map.
  - Click **Cancel** to cancel the delete function and return to the **SDS Configuration Destination Map** page.

If **OK** is clicked and any of the following conditions exist, an error message appears:

- Destination is in use by a route.

## Routing entities configuration

The **Routing Entities** page allows you to manage the supported routing entities:

- MSISDN
- IMSI
- IMSI Prefix
- MSISDN Prefix
- NAI User
- Wildcard NAI User Prefix

**Note:** A routing entity can be a standalone routing entity or a routing entity that is part of a subscriber (group of related routing entities and Account ID values).

From the **SDS Configuration Routing Entities** page, you can perform the following actions:

- Retrieve information for a specific Routing Entity.
- Add a supported Routing Entity.
- Update the information associated with an existing Routing Entity.
- Delete a Routing Entity.

### Routing entities configuration elements

This table describes the fields on the **SDS Configuration Routing Entities** page.

**Table 16: Routing Entities Configuration Elements**

Element	Description	Data Input Notes
Filter fields	Pulldown menu of available filters and additional fields to modify the search options.	Format: Selectable list
Type	Type of supported routing entity	Format: pulldown list Range: One of the following - MSISDN, IMSI, NAI User, Wildcard NAI User, MSISDN Prefix, IMSI Prefix <b>Note:</b> If <b>Type</b> is MSISDN or IMSI on the <b>Insert</b> or <b>Edit</b> pages and the Address is part of a Subscriber that has more than 1 MSISDN or IMSI routing entity, the update is automatically applied to all of the subscriber's MSISDN and IMSI routing entities.
Address (Except WC NAI User)	The routing entity address	Format: alphanumeric and underscore Range: Depends on Type <ul style="list-style-type: none"> <li>• MSISDN: 8–15 digits</li> <li>• IMSI: 10–15 digits</li> <li>• NAI User: 1–64 characters</li> <li>• MSISDN Prefix and IMSI Prefix: 1 - 15 digits</li> </ul>
Address Prefix (WC NAI User Only)	The routing entity address	Wildcard NAI User: 1–64 characters
NAI Host	NAI Host; available only when <b>NAI User</b> or <b>Wildcard NAI User</b> is selected as the <b>Type</b> It is not visible when <b>Type</b> is MSISDN, IMSI, MSISDN Prefix, or IMSI Prefix.	Format: pulldown list Range: available NAI Hosts
IMS HSS	IMS HSS destination	Format: pulldown list Range: available IMS HSS destinations

Element	Description	Data Input Notes
(available on the <b>Insert</b> page only)		
LTE HSS (available on the <b>Insert</b> page only)	LTE HSS destination	Format: pulldown list Range: available LTE HSS destination
PCRF (available on the <b>Insert</b> page only)	IMS HSS destination	Format: pulldown list Range: available PCRF destinations
OCS (available on the <b>Insert</b> page only)	IMS HSS destination	Format: pulldown list Range: available OCS destinations
OfCS (available on the <b>Insert</b> page only)	IMS HSS destination	Format: pulldown list Range: available OfCS destinations
AAA (available on the <b>Insert</b> page only)	IMS HSS destination	Format: pulldown list Range: available AAA destinations
User defined 1 (available on the <b>Insert</b> page only)	IMS HSS destination	Format: pulldown list Range: available User defined 1 destinations
User defined 2 (available on the <b>Insert</b> page only)	IMS HSS destination	Format: pulldown list Range: available User defined 2 destinations

### Retrieving routing entities

Use this process to retrieve route information.

You can perform this task when logged into an SDS or from the DP SOAM GUI.

Before performing this task, make sure Destinations and NAI Hosts have been configured.

1. Select **SDS > Configuration > Routing Entities**.  
The **SDS Configuration Routing Entities** page appears.
2. Select the type of routing entity from the **Type** pulldown list.
3. If NAI User or Wildcard NAI User is selected as the **Type**, select an NAI host from the **NAI Host** pulldown list.
4. Enter the route identifier for the routing entity in the **Address** or **Address Prefix** field.

**Note:** The **Address** field requirements depend on the type of blacklist routing entity. For more information on this field, see [Blacklist configuration elements](#).

5. Click **Go**.

When **Go** is clicked and the following condition exists, an error message appears:

- If either MSISDN or IMSI was selected as the **Type** and a non-digit character was entered.
- Field Address contains invalid characters.

## Adding routing entities

You can only perform this task when logged into the Active Primary SDS.

Before performing this task, make sure Destinations and NAI Hosts have been configured.

1. Select **SDS > Configuration > Routing Entities**.

The **SDS Configuration Routing Entities** page appears.

2. Click **Insert**.

The **SDS Configuration Routing Entities [Insert]** page appears.

3. Select the type of routing entity from the **Type** pulldown list.

4. Enter the route identifier for the routing entity in the **Address** or **Address Prefix** field.

**Note:** The **Address** field requirements depend on the type of blacklist routing entity. For more information on this field, see [Blacklist configuration elements](#).

5. If NAI User or Wildcard NAI User is selected as the **Type**, select a NAI host from the **NAI Host** pulldown list.

6. Select the associated destination(s) from the applicable destination(s) pulldown list.

At least one destination must be selected, although a destination can be selected for each of the destination types.

7. Perform one of the following:

- Click **OK** to save the connection and return to the **SDS Routing Entities** page.
- Click **Apply** to save the connection and remain on this page.
- Click **Cancel** to return to the **SDS Configuration Routing Entities** page without saving the changes.

If **OK** or **Apply** is clicked and any of the following conditions exist, an error message appears:

- Either MSISDN or IMSI was selected as the **Type** and a non-digit character was entered.
- At least one destination was not selected.
- Field Address contains invalid characters.

## Editing routing entities

You can only perform this task when logged into the Active Primary SDS.

1. Select **SDS > Configuration > Routing Entities**.

The **SDS Configuration Routing Entities** page appears.

2. Select the **Update** tab.

3. Select the type of routing entity from the **Type** pulldown list.
4. Enter the route identifier for the routing entity in the **Address** or **Address Prefix** field.  
**Note:** The **Address** or **Address Prefix** field requirements vary depending on the type of routing entity. For more information on this field, see [Routing entities configuration elements](#).
5. If NAI User or Wildcard NAI User is selected as the **Type**, select a NAI host from the **NAI Host** pulldown list.
6. Click **Lookup**.  
**Note:** If the route was not located during the **Lookup**, an error message appears.  
The **Update** tab appears with the routing entity information.
7. Edit the appropriate destination(s).  
For more information about these fields, see [Routing entities configuration elements](#).  
**Note:** Although at least one destination is required when adding a routing entity, there is no minimum requirement for destinations when updating the routing entity. For example, all of the destinations could possibly be set to **None**.
8. Click **Update**.

## Deleting routing entities

You can only perform this task when logged into the Active Primary SDS.

1. Select **SDS > Configuration > Routing Entities**.  
The **SDS Configuration Routing Entities** page appears.
2. Select the type of Routing Entity from the **Type** pulldown list.
3. If NAI User or Wildcard NAI User is selected as the **Type**, select NAI host from the **NAI Host** pulldown list.  
  
If **Type** is MSISDN or IMSI and the Address is part of a Subscriber that has more than 1 MSISDN and/or IMSI value, only the entered value is deleted (not all routing entities for the subscriber). If you want to delete the whole subscriber, you must do this from the **SDS > Configuration > Subscriber [Delete]**.  
  
If **Type** is MSISDN or IMSI and the Address is part of a Subscriber that has only 1 MSISDN or IMSI value, the routing entity will not be deleted; the subscriber must be deleted.
4. Type the **Address** of the Routing Entity you want to delete.
5. Click **Go**.  
**Note:** If the route was not located during the search, a message appears at the bottom of the screen.
6. Highlight the Routing Entity and click **Delete**.  
A popup confirmation window appears.
7. Perform one of the following actions:
  - Click **OK** to delete the connection.
  - Click **Cancel** to cancel the delete function and return to the **SDS Configuration Routing Entities** page.

If **OK** is clicked and any of the following conditions exist, an error message appears:

- Either MSISDN or IMSI was selected as the **Type** and a non-digit character was entered in the **Route** field
- The route identifier was not found.
- Field Address contains invalid characters.

## Subscribers

SDS Subscriber Identity Grouping (**Subscribers** page) allows you to group a customer-specified account ID, multiple MSISDN routing entities and multiple IMSI routing entities together into one Subscriber. After a Subscriber (a group of related routing entities and an optional Account ID value) is created, you can update destinations for all of the related routing entities, read all data from the subscriber and delete the subscriber by using any of the subscriber's addresses (for example, account ID, MSISDN, or IMSI). You can also modify addresses within a subscriber by specifying any of the subscriber's addresses.

Restrictions:

- This is a provisioning-only feature. For information, see *Subscriber Database Server Provisioning Interface*.

**Note:** You can only add a subscriber to a subscriber table, if the Account ID, MSISDN, or IMSI is not already in the table. If the table already contains any of these values, the add function fails and an error condition report is generated that contains the reason for the failure.

- The relationships between routing entities is only available on A-level servers, which are the SDS servers and the Query server.

The following restrictions apply to all Subscribers that contain a group of related MSISDN and IMSI routing entities and an optional Account ID. These rules do not apply to standalone routing entities.

- Every subscriber must have at least 1 routing entity (MSISDN or IMSI).
- All of the subscriber's routing entities must have the same destination values.
- Every subscriber can be accessed by specifying any of its routing entity values or its Account ID value.
- When you create a new subscriber, destinations are optional. If you do not specify a destination, destinations are set based upon the existing routing entities.
- All provisioning commands are for a single subscriber. All specified accountid, imsi, and msisdn values must be assigned to one subscriber or they can exist in a standalone routing entity.

From the **Subscriber** page, you can do the following:

- Retrieve information for a specific Subscriber.
- Create a Subscriber.
- Modify a previously defined Subscriber.
- Delete a selected Subscriber.

## Subscribers elements

Use the **SDS Configuration Subscribers** page to manage SDS Subscribers. This table describes fields on this page. Use the filter function to make initial selections for the elements you want to work with.

To add a Subscriber Table, use **Create** to indicate that a new insert is being performed.

**Note:** You can only add a subscriber to a subscriber table, if the Account ID, MSISDN, or IMSI is not already in the table. If the table already contains any of these values, the add function fails and an error condition report is generated that contains the reason for the failure.

**Table 17: Subscribers Elements**

Element	Description	Data Input Notes
Field	Type of data in the Value field used to find desired Subscriber (Account ID, MSISDN, IMSI)	Format: textbox One of the following - Account ID, MSISDN, or IMSI Default: Account ID
Value	The value of the Account ID, MSISDN ,or IMSI values for the subscriber	Format: Integer Range limits depends on Field value: <ul style="list-style-type: none"> <li>Account ID: 1-26 digits</li> <li>MSISDN: 8-15 digits</li> <li>IMSI: 10-15 digits</li> </ul> Default: blank Use <b>Add</b> , <b>Remove</b> , or <b>Clear All</b> to manipulate values within the fields.
Inherit Destinations (available on the <b>Insert</b> page only)	If checked, subscriber inherits destinations from specified routing entities.	Format: Check box Range: Checked, Unchecked Default: Unchecked
IMS HSS	IMS HSS destination	Format: pulldown list Range: available IMS HSS destinations
LTE HSS	LTE HSS destination	Format: pulldown list Range: available LTE HSS destination
PCRF	IMS HSS destination	Format: pulldown list Range: available PCRF destinations
OCS	IMS HSS destination	Format: pulldown list Range: available OCS destinations
OfCS	IMS HSS destination	Format: pulldown list Range: available OfCS destinations
AAA	IMS HSS destination	Format: pulldown list Range: available AAA destinations

Element	Description	Data Input Notes
User defined 1	IMS HSS destination	Format: pulldown list Range: available User defined 1 destinations
User defined 2	IMS HSS destination	Format: pulldown list Range: available User defined 2 destinations

### Retrieving subscribers

Use this process to retrieve information about a single Subscriber and all of the Subscriber's routing entities.

You can perform this task when logged into an SDS or from the DP SOAM GUI.

Before performing this task, make sure Destinations have been configured.

1. Select **SDS > Configuration > Subscribers**.  
The **SDS Configuration Subscribers** page appears.
2. Select the type of identifier from the **Display Filter** pulldown list.
3. Enter the subscriber identifier in the **Value** field.

**Note:** The **Value** field requirements depend on the type of identifier. For more information about this field, see [Subscribers elements](#).

4. Click **Go**.

When **Go** is clicked and the following condition exists, an error message appears:

- A non-digit was entered for the **Value** field.

### Adding subscribers

Use this process to create a new subscriber and group the specified MSISDN, IMSI, and Account ID values into one Subscriber record. The specified MSISDN and IMSI values can be for existing standalone or new MSISDN or IMSI routing entities. If the MSISDN or IMSI value does not exist as a standalone routing entity, the routing entity is automatically added, and the MSISDN or IMSI value is added to the Subscriber. All destination values from existing standalone routing entities must be the same before applying the values you enter on the **Subscribers Create** page.

Specifying destinations is optional. You can check the **Inherit Destinations** checkbox to inherit the current destination values from a subscriber's existing routing entity.

Before performing this task, make sure Destinations have been configured.

If no MSISDN or IMSI values currently exist as a standalone entry, then at least one destination must be provided.

At least one MSISDN or IMSI value must exist for the Subscriber.

1. Select **SDS > Configuration > Subscribers**.  
The **SDS Configuration Subscribers** page appears.

2. Click **Insert**.  
The **SDS Configuration Subscribers [Insert]** page appears.
  3. Enter an **Account ID** to associate a unique number to the Subscriber's account.  
**Note:** This is an optional field and contains a value 1-26 digits in length.
  4. Enter MSISDN values to associate MSISDNs with the subscriber. Click **Add**, **Remove**, or **Clear All** to implement your updates. A maximum of 6 MSISDNs are supported. At least one destination must be provided when creating a new MSISDN or IMSI.
  5. Enter IMSI values to associate IMSIs with the subscriber. Click **Add**, **Remove**, or **Clear All** to implement your updates. A maximum of 6 IMSIs are supported. At least one destination must be provided when creating a new MSISDN or IMSI.
  6. Optionally, select **Inherit Destination** to inherit the current destination values from a subscriber's existing routing entity.  
**Note:** The base field set information that appears here is for display purposes only. See [Table 17: Subscribers Elements](#) for more information on each field.
  7. Select from any of the following pulldown lists to name one of each type of destination.
    - **IMS HHS**
    - **LTE HSS**
    - **PCRF**
    - **OCS**
    - **OfCS**
    - **AAA**
    - **User defined 1**
    - **User defined 2**
  8. Perform one of the following:
    - Click **OK** to save the connection and return to the **SDS Configuration Subscribers** page.
    - Click **Apply** to save the connection and remain on this page.
    - Click **Cancel** to return to the **SDS Configuration Subscribers** page without saving the changes.
- If field validations succeed, the subscriber is saved. If **OK** or **Apply** is clicked and any of the following conditions exist, an error message appears:
- Either MSISDN or IMSI was selected as the **Type** and a non-digit character was entered.
  - At least one destination was not selected.
  - Field Address contains invalid characters.

## Editing subscribers

This page allows you to locate and modify a single Subscriber.

Use this procedure to update the identification (MSISDN, IMSI, and Account ID) values for a Subscriber and/or update the Subscriber's destination values.

1. Select **SDS > Configuration > Subscribers**.  
The **SDS Configuration Subscribers** page appears.

2. Select a **Display Filter** from the pulldown list and type the corresponding address or identification number.
3. Click **Go**.  
**Note:** If a subscriber was not located during the search, a message appears at the bottom of the screen.
4. Highlight the Subscriber you want to edit and click **Edit**.  
The **SDS Configuration Subscribers [Edit]** page appears.
5. Edit the information you want to change.  
For more information about these fields, see [Routing entities configuration elements](#).  
**Note:** Although at least one destination is required when adding a subscriber, there is no minimum requirement for destinations when updating the subscriber. For example, all of the destinations could possibly be set to **None**.
6. Click **OK** or **Cancel**.  
The **SDS Configuration Subscribers** page appears.

## Deleting subscribers

Follow these steps to delete the Subscriber and all of the Subscriber's routing entities.

**Note:** Global Data Delete permission is required for this function.

1. Select **SDS > Configuration > Subscriber**.  
The **SDS Configuration Subscriber** page appears.
2. Select a **Display Filter** from the pulldown list and type the corresponding address or identification number.
3. Click **Go**.  
**Note:** If a subscriber was not located during the search, a message appears at the bottom of the screen.
4. Highlight the Subscriber you want to delete and click **Delete**.  
A popup confirmation window appears.
5. Perform one of the following actions:
  - Click **OK** to delete the Subscriber.
  - Click **Cancel** to cancel the delete function and return to the **SDS Configuration Subscriber** page.

After you click **Delete**, a warning dialog box displays indicating all associated MSISDNs and IMSIs are also deleted.

## Blacklist

The Blacklist function (**SDS Configuration Blacklist** page) allows you to provision IMSI and MSISDN Blacklist values that can be searched before searching the MSISDN or IMSI Routing Entities to determine if a value is blacklisted.

Both MSISDN and IMSI blacklist data are supported in SDS/DP systems.

From the **SDS Configuration Blacklist** page, you can perform the following actions:

- Retrieve a previously defined blacklist value
- Add a new blacklist value
- Delete an existing blacklist value

### Blacklist configuration elements

This table describes the fields on the **SDS Configuration Blacklist** page.

**Table 18: Blacklist Configuration Elements**

Element	Description	Data Input Notes
Type	Type of routing entity to blacklist	Format: pulldown list Range: One of the following - MSISDN or IMSI
Address	The routing entity address	Format: alphanumeric and underscore Range: Depends on Type <ul style="list-style-type: none"> <li>• MSISDN: 8–15 digits</li> <li>• IMSI: 10–15 digits</li> </ul>

### Retrieving blacklist values

Follow these steps to retrieve a single MSISDN or IMSI Blacklist value. These are values that are not routed to a destination.

1. Select **SDS > Configuration > Blacklist**.  
The **SDS Configuration Blacklist** page appears.
2. Select the type of blacklist routing entity from the **Type** pulldown list.
3. Enter the route identifier for the routing entity in the **Address** field.

**Note:** The **Address** field requirements depend on the type of blacklist routing entity. For more information on this field, see [Blacklist configuration elements](#).

4. Click **Go**.

When **Go** is clicked and the following condition exists, an error message appears:

- If a non-digit character was entered for the **Value** field.

### Adding blacklist values

Follow these steps to add a single MSISDN or IMSI Blacklist value. These are values that will not be routed to a destination.

1. Select **SDS > Configuration > Blacklist**.  
The **SDS Configuration Blacklist** page appears.

2. Click **Insert**.  
The **SDS Configuration Subscribers [Insert]** page appears.
3. Select the type of blacklist routing entity from the **Type** pulldown list.
4. Enter the blacklist route identifier for the routing entity in the **Address** field.  
**Note:** The **Address** field requirements depend on the type of blacklist routing entity. For more information on this field, see [Blacklist configuration elements](#).  
**Note:** .
5. Perform one of the following:
  - Click **OK** to save the connection and return to the **SDS Configuration Blacklist** page.
  - Click **Apply** to save the connection and remain on this page.
  - Click **Cancel** to return to the **SDS Configuration Blacklist** page without saving the changes.If field validations succeed, the blacklist value is saved. If **OK** or **Apply** is clicked and any of the following conditions exist, an error message appears:
  - If a non-digit character was entered.
  - The value entered for the MSISDN or IMSI value already exists in the routing entities table.

## Deleting blacklist values

Follow these steps to delete a single MSISDN or IMSI Blacklist value

**Note:** Global Data Delete permission is required for this function.

1. Select **SDS > Configuration > Blacklist**.  
The **SDS Configuration Blacklist** page appears.
2. Select the type of Routing Entity from the **Type** pulldown list.
3. Type the **Address** of the Routing Entity you want to delete.
4. Click **Go**.  
**Note:** If the route was not located during the search, a message appears at the bottom of the screen.
5. Highlight the Routing Entity you no longer want to Blacklist and click **Delete**.  
A popup confirmation window appears.
6. Perform one of the following actions:
  - Click **OK** to delete the blacklist
  - Click **Cancel** to cancel the delete function and return to the **SDS Configuration Blacklist** page.If **OK** is clicked and any of the following conditions exist, an error message appears:
  - If a non-digit character was entered.
  - The route identifier was not found.
  - **Address** contains invalid characters.

## Maintenance

---

**Topics:**

- [Connections maintenance.....60](#)
- [Command log maintenance.....62](#)
- [Relay exception log.....65](#)
- [Import status maintenance.....66](#)
- [Export schedule and status maintenance.....68](#)
- [Remote audit.....75](#)
- [Query .....79](#)
- [NPA Splits maintenance.....83](#)

The **Maintenance** menu options allow you to query and audit data, view up-to-date status of the database and various features, and initiate import and exports.

From the maintenance menu on an SDS you can:

- Query the database for specified:
  - MSISDN
  - MSISDN Prefix
  - MSISDN Blacklist
  - IMSI
  - IMSI Prefix
  - IMSI Blacklist
  - NAI user
  - Wildcard NAI user ranges
- View provisioning connections, command logs, relay exception logs, and the status of imports and exports
- Configure and manage NPA Splits
- Schedule exports, including command logs
- Perform remote audits

When you are logged into an DP SOAM you cannot request a remote audit, update splits, or schedule an export on the DP SOAM GUI.

The available menu options vary based on the type of server you are logged into and the permissions assigned to your group. If you do not see a menu option you need, make sure you are logged into the appropriate type of server and ask your administrator to make sure the group your user ID belongs to has the appropriate permissions.

The **SDS Maintenance** pages provide maintenance information related to provisioning connections and data. With this page you can monitor provisioning

connections; view every provisioning message exchanged between provisioning systems in the command log; view the status of imports and exports; open import and export files; and import result logs.

All provisioning maintenance tasks are only available when logged into an SDS.

## Connections maintenance

The **SDS > Maintenance > Connections** page allows you to view the currently-in-use external connections. A list of all provisioning connections established to the system can be viewed. A display filter can be applied for a specified search. The information is displayed in tables.

Any local connections (including the one from the GUI itself) are not included.

### Connections maintenance elements

[Table 19: Connections Maintenance Elements](#) describes elements on the **SDS > Maintenance > Connections** page.

**Table 19: Connections Maintenance Elements**

Element	Description	Data Input Notes
Timestamp	Time the connection was established	Format: Year-Month-Day Hour-Minute-Second
CID	Connection ID	N/A
Remote IP Address	IP address for the remote client	<p>Format: Valid IP address</p> <p>Range: Either an IPv4 or an IPv6 IP address.</p> <p>IPv4 addresses are 32 bits, represented in a dot-decimal notation like this: x.x.x.x where each x (called an octet) is a decimal value from 0 to 255. They are separated by periods. For example: 1.2.3.4 and 192.168.0.100 are valid IPv4 addresses.</p> <p>IPv6 addresses are 128 bits, represented in a colon-hexadecimal notation like this: z::z::z::z::z where each z is a group of hexadecimal digits ranging from 0 to ffff. They are separated by colons. Leading zeros may be omitted in each group. "::" can be used (at most once) in an IPv6 address to represent a range of as many zero fields as needed to populate the address to eight fields. So the IPv6 address 2001:db8:c18:1:260:3eff:fe47:1530 can also be represented as 2001:0db8:0c18:0001:0260:3eff:0fe47:1530 and the IPv6 address ::1 is the same as 0000:0000:0000:0000:0000:0000:0000:0001</p>
Remote Port	Port used for the remote client connection	Format: Valid port number
Version	Version of API this client application is using	Default: 1.0

Element	Description	Data Input Notes
Txn Mode	Database transaction mode	Range: <ul style="list-style-type: none"> <li>• normal: All updates must be sent inside a transaction explicitly begun and ended by begin_txn and end_txn/abort_txn requests respectively.</li> <li>• single: Transactions are implicitly begun and ended for individual update requests</li> </ul> Default: normal
Cnx Manager	Connection manager	Options: Pdba, Xds, XmlImport, XmlExport, PdbRelay, PdbAudit
Idle Timeout	Number of minutes the connection can be idle before it is automatically timed out	Range: <ul style="list-style-type: none"> <li>• 0 (the connection is never terminated)</li> <li>• 1 - 44640 minutes</li> </ul> Default: 0

### Viewing connections status

Use this task to view a list all provisioning connections established to the system. The listing of connections may be filtered.

1. Select **SDS > Maintenance > Connections**.  
The **SDS Maintenance Connections** page appears. All provisioning connections are displayed in the table. Click on any column heading to reorder the rows.
2. To look for a specific connection, click **Filter**.
3. Select the category to perform the filtering.  
The fields are described in [Connections maintenance elements](#).
4. Choose the filtering operator.

**Table 20: Connections Status Filtering Operators**

Operator	Description
=	Is equal to
!=	Is not equal to
>	Is greater than
>=	Is equal to or greater than
<	Is less than
<=	Is equal to or less than
Like	Is Like (wildcard is * character)

Operator	Description
Is Null	has no entry (is zero)

5. Enter the target character string to filter on in the text box.
6. Click **Go** to show results.

## Command log maintenance

The **SDS > Maintenance > Command Log** page shows a table containing a history of commands and their responses. This table shows the **Timestamp**, **System ID**, **CID**, and the **Text** of the commands received from both remote and local connections, including the GUI.

You can view provisioning logs of SDS data being provisioned from various sources. Also, you can export these provisioning logs.

To enable provisioning commands logging (including their responses), you must activate that functionality. Upon feature activation, the command log information is visible on the GUI. Each provisioning command has a response, both of which are stored in the command log information database. The rate of log table export is related to the **System ID** set in the **SDS > Configuration > Connections** page.

When calculating the command log export parameters, consider the following:

- When the storage table is full, new entries begin to overwrite newer entries overwrite the oldest entries.
- The table should be exported frequently enough to avoid information loss, but not so frequently that it becomes a resource drain.
- Consider the rate of command/response pairs when setting the log export parameters.
- It is recommended to export the command log data on a daily basis.

To prevent loss of data, you should export the logs before the data is overwritten by the latest entry in table after the table is filled completely. Based on the system usage, you can calculate when the records reach the throttle limit and logs need to be exported. If the log or logs reaches the throttling limit in one day, you must ensure to export the data on daily basis. Typical rates observed in the field tend to be close to 20 commands/second. Based on that rate, the command log would wrap in close to 3 days.

You can calculate your system setup's throttle limits to help determine when logs should be exported. Based on typical in-field throttle rates, a 2 GB table can store 5 million comments. If the system on average takes  $x$  commands per seconds, then the table will be overwritten by the latest entry in:

$$5000000/x \text{ seconds} = 83333/x \text{ minutes} = 1389/x \text{ hours} = 58/x \text{ days (where } x \text{ is the commands per second)}$$

Every provisioning message exchanged between provisioning systems is written to the command log and is stored for up to seven days.

## Command log maintenance elements

[Table 21: Command Log Maintenance Elements](#) describes elements on the SDS > Maintenance > Command Log page.

**Table 21: Command Log Maintenance Elements**

Element	Description
Timestamp	Date and time the command was logged
System ID	System identifier of the originating client
CID	Client connection identifier
Text	Exact command and response message

## Viewing maintenance command logs history

Use this task to view a history list of commands and their responses. The history is displayed as a table showing the **Timestamp**, **System ID**, **CID**, and **Text** of the commands received from both remote and local connections, including the GUI. The history may be filtered by category.

**Note:** You can check mark the **Pause updates** check box to temporarily stop this command log from being updated.

1. Select **SDS > Maintenance > Command Log**.  
The **SDS Maintenance Command Log** page appears.
2. Click **Show Errors** at the bottom of the table to display only the error responses out of all the records.
3. To look for a specific log, click **Filter**.
4. Select the category to perform the filtering.  
The fields are described in [Table 21: Command Log Maintenance Elements](#).
5. Choose the filtering operator.

**Table 22: Command Log Filtering Operators**

Operator	Description
=	Is equal to
Like	Is Like (wildcard is * character)

6. Enter the target character string to filter on in the text box.
7. Enter the maximum number of records to display.
8. Mark the **Time Range** checkbox and enter a date range of the records to display.
9. Click **Go** to show results.  
The **SDS Maintenance Command Log (Filtered)** page displays with the results.

## Exporting maintenance command logs

Use this task to export provisioning log commands and their responses to a database. The exported files are copied to a remote server. This is a server other than the single remote server supported by APDE. The files are then deleted from the local system after the transfer is complete. Files exported to the file management area can be viewed and imported on the local system.

**Note:** The export file is in CSV format.

1. Select **SDS > Maintenance > Command Log**.  
The **SDS Maintenance Command Log** page appears.
2. Click **Export**. The **SDS Maintenance Command Log [Export]** page appears.
3. Choose the filtering operators to filter and control command log exportation functionality.  
The fields are described in [Table 23: Exporting Command Log Filtering Operators](#).

**Table 23: Exporting Command Log Filtering Operators**

Operator	Description
None	No filter
System ID	View exported logs by System ID
CID	View exported logs by CID
Log Text	View exported logs by Log Text

4. Enter the maximum number of records to display.
5. Enter the export logs value for last number of hours.
6. Set the export frequency to determine to select how often the data is written to the export directory.  
The export frequency gives you a way to limit the size of the export to a configurable number of hours prior to the start of the export. This helps you control system resources that are used for the export function.
7. Enter a periodic export task name.
8. Enter a name for this export file.
9. Enter a periodic export task description.
10. Select the directory in which the export file or files will be placed. Exported files are automatically overwritten in the **Data Export Server Directory** if the remote server is set up. The files are then deleted from the local system after the transfer. Files exported to the **File Management Directory** can be viewed and imported on the local system.  
The Remote Server is configured through Multiple Export Server on the **Administration -> Remote Servers -> Data Export** page..  
See *Operations, Administration, and Maintenance (OAM) User's Guide* for information about Multiple Export Server and Filename Prefix. Filename Prefix is an optional export filename prefix that pre-pends the generated export filename.
11. Select the minute of each hour when the data is written to the export directory.
12. Select the time of day when the data is written to the export directory.
13. Select the day of week when the data is written to the export directory.

- 14. Click OK.

## Relay exception log

The **SDS > Maintenance > Relay Exception Log** page shows a table containing all types of exceptions (unexpected results) found while processing SDS to HLRR relay or export functionality. Consequently, all fields do not always contain data. All entries in the Relay Exception Log contain enough data so you can determine what SDS data caused the exception.

Ideally, the Relay Exception Log would be empty, which means SDS has all of the data required to create an HLRR provisioning command and all of the required Network Entities are provisioned for the HLR Router. Because the most likely cause of an error would be associated with relaying new provisioning commands to HLRR, the Relay Exception Log displays column headings for exceptions created by `pdbrelay`. Deviations for other creators include:

- If no command is relayed to HLRR, the Derived Relay Request value is `None`.
- If the Creator value is not equal to `pdbrelay`, the Derived Relay Request value from the SDS Command Log section is blank.

## Relay Exception Log maintenance elements

*Table 24: Exception Log Maintenance Elements* contains a list of exceptions found while processing data that should be relayed from SDS to HLRR on the **SDS > Maintenance > Relay Exception Log** page.

**Note:** Display limit must be a numeric integer greater than zero.

**Table 24: Exception Log Maintenance Elements**

Element	Description
Timestamp	Date and time when the exception occurred
Seq Num	Exception sequence number
Creator	Name of process that created the exception
Reason	Reason the exception was created
Derived Relay Request	Command created and relayed to HLR Router
Command	Command text from the SDS Command Log
Seq Num	Sequence number form the SDS Command Log
Timestamp	Timestamp from the SDS Command Log

## Viewing relay exception logs history

Use this task to view a list of information of a history of commands and their responses. The history is displayed as a table showing the **Timestamp**, **System ID**, **CID**, and the **Text** of the commands

received from both remote and local connections, including the GUI. The history may be filtered by category.

**Note:** You can check mark the **Pause updates** check box to temporarily stop this command log from being updated.

1. Select **SDS > Maintenance > Relay Exception Log**.  
The **SDS Maintenance Relay Exception Log** page appears.
2. To look for a specific log, click **Filter**.
3. Select the category by which to perform the filtering.  
The fields are described in [Table 24: Exception Log Maintenance Elements](#).
4. Choose the filtering operator.

**Table 25: Relay Exception Log Filtering Operators**

Operator	Description
=	Is equal to
Like	Is Like (wildcard is * character)

5. Enter the target character string to filter on in the text box.
6. Enter the maximum number of records to display.
7. Mark the **Time Range** checkbox and enter a date range of the records to display.
8. Click **Go** to show results.  
The **SDS Maintenance Relay Exception Log (Filtered)** page displays with the results.

## Import status maintenance

Allows an operator to view the status of all Imports.

Data can be imported from a provisioning import file to add new, or update existing, data in the database. Imports are not scheduled through the user interface but import settings are configured with the provisioning options page.

Import files that are placed in a specific location on a remote server (**Remote Import Directory**) are detected within five minutes and automatically downloaded via SSH File Transfer Protocol (SFTP) to the file management storage area. For a file to be imported, it must:

- be properly named following the naming convention. For more information see the SDS Administration Manual.
- have been placed in the remote directory after the time when provisioning import last ran
- must not have been previously imported. A file that has already been imported into the local directory will not be imported again, even if its status is Failed.

**Note:** To import a previously Failed file, correct the file as necessary, rename the file, and then place the renamed file in the remote directory.

Once fully downloaded, each file is automatically imported into the Provisioning Database sequentially in the order in which their download completed. The provisioning import file is an ASCII text file containing a series of database manipulation requests in provisioning format.

The **SDS Maintenance Import Status** page allows you to view the status of provisioning imports. Import records with a status of Completed or Failed can be deleted from this table.

### Import status maintenance elements

*Table 26: Import Status Maintenance Elements* describes elements on the **SDS > Maintenance > Import Status** page.

**Table 26: Import Status Maintenance Elements**

Element	Description
Import File	Name of import file
Time Queued	Time the import was queued
Time Started	Time the import started
Time Completed	Time the import completed
Success Count	Number of successful import commands
Fail Count	Number of unsuccessful import commands
Progress	Percentage of import progress
Result Log	Name/heading of result log
Status	Status of the import

### Viewing import status files

This task allows you to view the status of all Imports. Imports are not scheduled through the GUI. They are initiated by the presence of a file placed in the Remote Import Directory.

- If the filename in the **Import File** or **Result Log** column exceeds 24 characters, it is truncated at 22 characters and the characters “...” are appended to the end of the truncated string to signify the filename was truncated.
- The filenames in both the **Import File** or **Result Log** columns are hyperlinks. You can click on the links to view the files as text or to save them locally.
- You cannot edit an imported file using this form.
- You may delete an Import Status record if the **Status** is **Completed**, or **Failed**.

**1. Select SDS > Maintenance > Import Status.**

The **SDS Maintenance Import Status** page appears. Click on any column heading to reorder the rows.

2. To look for a specific import, click **Filter**.
3. Select the category to perform the filtering.

The fields are described in [Table 26: Import Status Maintenance Elements](#).

4. Choose the filtering operator.

**Table 27: Connection Status Filtering Operators**

Operator	Description
=	Is equal to
!=	Is not equal to
>	Is greater than
>=	Is equal to or greater than
<	Is less than
<=	Is equal to or less than
Like	Is Like (wildcard is * character)
Is Null	has no entry (is zero)

5. Enter the target character string to filter on in the text box.
6. Click **Go** to show results.
7. To delete an import record, select a record and click **Delete**.

**Note:** The import record can only be deleted if the **Status** is **Completed** or **Failed**. A popup confirmation dialog appears. For all other imports, the **Delete** action is inactive (grayed-out).

A confirmation dialog to complete the delete action appears. For all other imports, the **Delete** action is inactive (grayed-out).

## Export schedule and status maintenance

Provisioning data can be exported to an ASCII file in either XML or CVS format using the application user interface. The **SDS Maintenance Export** pages allow you to view the status, progress, and data count information for scheduled provisioning exports. You may use exported records to do data manipulation of subscriber data.

**Note:** Export is a time consuming operation recommended to be scheduled during off-peak hours. SDS operators can schedule one-time or recurring exports.

Exported data may also be offloaded to a remote server. The exported text file is also available to be downloaded from the 'file transfer area.' Export is a periodic task. Any changes done to the export table take effect on next export period. The following is the functionality of Export:

- You can configure and schedule data export on daily, weekly, or monthly.
- The exported files are sFTPed or transferred via SSH to a server configured on SDS.
- Data can be exported to a file in XML, CSV, or HLRR formats to be used as import files for an HLRR.

- You can export subscriber data (in XML or CSV format) as shown in [Table 28: Interfaces for Subscriber Data Types](#):

**Table 28: Interfaces for Subscriber Data Types**

Subscriber Data Type	GUI (add, change, delete and query)	SOAP and/or XML (add, change, delete and query)	XML Export and Import	CSV Export and Import	SQL Query (from Query Server)	HLRR
MSISDN	yes	yes	yes	yes	yes	yes
IMSI	yes	yes	yes	yes	yes	yes
NAI User	yes	yes	yes	yes	yes	no
Wildcard NAI User	yes	no	no	yes	yes	no
NAI Host	yes	no	no	yes	yes	no
Destination	yes	no	no	yes	yes	no
Destination Map	yes	no	no	no	yes	no
MSISDN Prefix	yes	no	no	yes	yes	no
IMSI Prefix	yes	no	no	yes	yes	no
MSISDN Blacklist	yes	no	no	yes	yes	no
IMSI Prefix	yes	no	no	yes	yes	no
Subscriber	yes	yes	yes	yes	yes	no

## Export Schedule

The **SDS > Maintenance > Export Schedule** page displays information for all exports scheduled for this system.

### Export schedule maintenance elements

[Table 29: Export Schedule Maintenance Elements](#) describes elements on the **SDS > Maintenance > Export Schedule** page.

**Table 29: Export Schedule Maintenance Elements**

Element	Description
Identifier	Name of export file
File format	Format of the export file (CSV, XML, or HLRR)
Export Data	Type of data to export
First Export	The first time this export is scheduled to run
Next Export	The next time this export is scheduled to run
Repeat	How often to repeat export
Comment	Purpose of export

### Viewing export schedule

The **SDS > Maintenance > Export Schedule** page shows the scheduled exports for this system.

1. Select **SDS > Maintenance > Export Schedule**.

The **SDS Maintenance Export Schedule** page appears with all exports displayed as a table. Click on any column heading to reorder the rows.

2. To look for a specific export schedule, click **Filter**.

3. Select the category to perform the filtering.

The fields are described in [Table 29: Export Schedule Maintenance Elements](#).

4. Choose the filtering operator.

**Table 30: Export Schedule Filtering Operators**

Operator	Description
=	Is equal to
!=	Is not equal to
>	Is greater than
>=	Is equal to or greater than
<	Is less than
<=	Is equal to or less than
Like	Is Like (wildcard is * character)
Is Null	has no entry (is zero)

5. Enter the target character string to filter on in the text box.
6. Click **Go** to show results.

### Inserting an export schedule

The **SDS > Maintenance > Export Schedule [Insert]** page allows you to create an export for this system.

The field or fields highlighted in yellow are keys and must be unique within this table in order to be successful. Fields marked with a red asterisk (\*) require a value.

1. Select **SDS > Maintenance > Export Schedule**.  
The **SDS Maintenance Export Schedule** page appears.
2. Click **Insert** located on the bottom of the page.  
The **SDS Maintenance Export Schedule [Insert]** page appears.
3. Enter an identifying string for the scheduled export in the **Identifier** text box.  
The identifier must be 4 to 12 characters.
4. Use the radio buttons **csv**, **xml**, or **hlrr** to select the **File Format** of the export file.
5. Use the drop down lists to select the initial date at which this export should run.
6. Use the drop down lists to select the initial time at which this export should run.
7. From the **Export Data** drop down list, select the type of data to be exported.  
The available type data selections are csv or xml file format.

**Table 31: Export Data Types**

Type of Data	CSV Format	XML Format	HLRR Format
All	X	X	X
MSISDN	X	X	X
MSISDN Blacklist	X		
MSISDN Prefix	X		
IMSI	X	X	X
IMSI Blacklist	X		
IMSI Prefix	X		
NAI User	X	X	
Wildcard NAI User	X		
NAI Host	X		
Destinations	X		
Subscriber	X	X	

**Note:** For HLRR-formatted exports of "All" data, a pop-up appears warning that, because of updates to the PDB Relay Timestamp, the HLRR-formatted exports must only be run as part of the HLR Router Bulk Load Procedure.

**Note:** For HLRR-formatted exports of "All" data, the PDB Relay feature must be disabled before an export will succeed.

8. Use the radio buttons **None**, **Daily**, **Weekly**, or **Monthly** to select how often this export should be repeated.
9. In the Comment text box, enter text that may be used to describe the purpose of this export.  
**Note:** You can enter up to 255 characters for a comment.
10. Perform one of these actions:
  - Click **OK**. If field validations succeed, the new export is saved and the previous page appears. If the page contains any values that are not valid, or if a required field is empty, an error message appears.
  - Click **Apply**. If field validations succeed, the new export is saved and you remain on the same page.
  - Click **Cancel** to abort changes on this page and return to the previous page.

### Editing an export schedule

The **SDS > Maintenance > Export Schedule [Edit]** page allows you to manually change an existing export job by editing an entry in the Export Schedule.

The field or fields highlighted in yellow are keys and must be unique within this table to be successful. Fields marked with a red asterisk (\*) require a value.

1. Select **SDS > Maintenance > Export Schedule**.  
 The **SDS Maintenance Export Schedule** page appears.
2. Highlight the export you want to edit and click **Edit**.  
 The **SDS Maintenance Export Schedule [Edit]** page appears.
3. Enter an identifying string for the scheduled export in the **Identifier** text box.  
 The identifier must be 4 to 12 characters.
4. Use the radio buttons **csv**, **xml**, or **hlrr** to select the **File Format** of the export file.
5. Use the appropriate drop down list to select the initial date at which this export should run.
6. Use the appropriate drop down list to select the initial time at which this export should run.
7. From the **Export Data** drop down list, select the type of data to be exported.

The available type data selections are csv and xml file format.

**Table 32: Export Data Types**

Type of Data	CSV Format	XML Format	HLRR Format
All	X	X	X
MSISDN	X	X	X
MSISDN Blacklist	X		
MSISDN Prefix	X		
IMSI	X	X	X
IMSI Blacklist	X		

Type of Data	CSV Format	XML Format	HLRR Format
IMSI Prefix	X		
NAI User	X	X	
Wildcard NAI User	X		
NAI Host	X		
Destinations	X		
Subscriber	X	X	

8. Use the radio buttons **None**, **Daily**, **Weekly**, or **Monthly** to select how often this export should be repeated.
9. In the Comment text box, enter text to describe the purpose of this export.  
**Note:** You can enter up to 255 characters for a comment.
10. Perform one of these actions:
  - Click **OK**. If field validations succeed, the new export is saved and the previous page appears. If the page contains any values that are not valid, or if a required field is empty, an error message appears.
  - Click **Cancel** to abort changes on this page and return to the previous page.

### Deleting an export schedule

The **SDS > Maintenance > Export Schedule [Delete]** page allows you to manually delete an export job by deleting an entry from the Export Schedule Table.

1. Select **SDS > Maintenance > Export Schedule**.  
 The **SDS Maintenance Export Schedule** page appears.
2. Highlight the destination you want to delete and click **Delete**.  
 A popup confirmation window appears.
3. Perform one of the following actions:
  - Click **OK** to confirm the action to delete the export record and return to the **SDS > Maintenance > Export Schedule** page.
  - Click **Cancel** to abort the delete action and return to the **SDS > Maintenance > Export Schedule** page.

### Export Status

The **SDS > Maintenance > Export > Status** page shows all in-progress and completed scheduled exports in this system.

### Export status maintenance elements

*Table 33: Export Status Maintenance Elements* describes elements on the **SDS > Maintenance > Export Status** page.

**Table 33: Export Status Maintenance Elements**

Element	Description
Export File	Name of export file
Time Queued	Time the export was queued
Time Started	Time the export started
Time Completed	Time the export completed
Subscribers	Number of exported Subscribers
MSISDNs	Number of MSISDNS exported
IMSI	Number of IMSIs exported
MSISDN Prefix	Number of MSISDI Prefixes exported
IMSI Prefix	Number of IMSI Prefixes exported
MSISDN Blacklist	Number of MSISDI Blacklists exported
IMSI Blacklist	Number of IMSI Blacklists exported
NAI Hosts	Number of NAI Hosts exported
NAI Users	Number of NAI Users exported
Wildcard NAIs	Number of Wildcard NAIs exported
Destinations	Number of Destinations exported
Status	Status of export
Comment	Descriptive text about export. This field is optional, so it may be blank.

### Viewing export status

The **SDS > Maintenance > Export Status** page shows the status of all in-progress and completed scheduled exports for this system.

- If the filename in the **Export File** column exceeds 24 characters, it is truncated at 22 characters and the characters “...” are appended to the end of the truncated string to signify the filename was truncated.
- The filenames in the **Export File** column are hyperlinks. You can click on the links to view the files as text or to save them locally.
- You can not modify or delete an export record using this form.
- Records are automatically removed after 7 days.

1. Select **SDS > Maintenance > Export Status**.

The **SDS Maintenance Export Status** page appears with all exports displayed as a table. Click on any column heading to reorder the rows.

2. To look for a specific export status, click **Filter**.
3. Select the category by which to perform the filtering.  
The fields are described in [Table 33: Export Status Maintenance Elements](#).
4. Choose the filtering operator.

**Table 34: Export Status Filtering Operators**

Operator	Description
=	Is equal to
!=	Is not equal to
>	Is greater than
>=	Is equal to or greater than
<	Is less than
<=	Is equal to or less than
Like	Is Like (wildcard is * character)
Is Null	has no entry (is zero)

5. Enter the target character string to filter on in the text box.
6. Click **Go** to show results.

## Remote audit

The **SDS Maintenance Remote Audit** page allows you to access an on-demand ability to initiate an audit of the remote HLR Router provisioning database and flag any differences found between the SDS and the HLR Router databases. This provisioning database audit includes MSISDNs and IMSIs and their associated Network Entity address values, which are extracted from the Destination Map table.

When you submit an audit request on the SDS GUI maintenance page, a PDBI client called *pdbaudit* connects to the local PDBA and to the remote PDBA running on the HLR Router system. It sends request commands to both PDBAs, compares the response data, and reports any discrepancies between the two databases. Then you can check the status and review the results of the audit on the SDS GUI status page.

SDS supports manual audit runs between the SDS master database instance and the HLR Router database instance. Configurable automated audit runs are those runs that run at configured times to verify the accuracy of SDS master and HLR Router database instances. A manual audit allows specification of audit between SDS master and HLR Router database instances, based on some data range (for example, audit IMSI range) or single MSISDN or IMSI value.

SDS supports an on-demand ability to initiate an audit of the remote HLR Router provisioning database and flag any differences found between the SDS and the HLR Router databases. HLR Router provisioning data to be audited can be specified in one of two ways - by a single range of numbers, or by an input file containing multiple ranges of numbers. Using an input file allows an operator to specify multiple IMSI and MSISDN ranges at one time versus scheduling multiple remote HLR Router audits on a single range.

Use the **SDS Maintenance Remote Audit** page to:

- View the status of the database remote audits and to request a site-wide database audit of a specified subset of provisioning data, and/or
- Request a remote audit between SDS and HLR Router data using a subset of MSISDN or IMSI values.

Since each node is responsible for managing its own resources, some nodes may decide to delay or cancel the requested audit to maintain sufficient resources to process signaling traffic.

### Remote audit elements

*Table 35: Remote Audit Elements* describes the elements on the **SDS > Maintenance > Remote Audit** page.

**Table 35: Remote Audit Elements**

Element	Description	Data Input Notes
Type	Type of data being audited	Format: MSISDN or IMSI
Range/File	Range of data being audited or file name containing ranges of data being audited	Format: Digits only Range: 8 - 15 digits for MSISDN Range: 10 - 15 for IMSI
Remote IP	IP address for Remote HLR Router system used for auditing	Format: Digits only Range: Either an IPv4 or an IPv6 IP address. IPv4 addresses are 32 bits, represented in a dot-decimal notation like this: x.x.x.x where each x (called an octet) is a decimal value from 0 to 255. They are separated by periods. For example: 1.2.3.4 and 192.168.1.100 are valid IPv4 addresses. IPv6 addresses are 128 bits, represented in a colon-hexadecimal notation like this: z:z:z:z:z:z:z:z where each z is a group of hexadecimal digits ranging from 0 to ffff. They are separated by colons. Leading zeros may be omitted in each group. "::" can be used (at most once) in an IPv6 address to represent a range of as many zero fields as needed to populate the address to eight fields. So the IPv6 address 2001:db8:c18:1:260:3eff:fe47:1530 can also be

Element	Description	Data Input Notes
		represented as 2001:0db8:0c18:0001:0260:3eff:fe47:1530 and the IPv6 address ::1 is the same as 0000:0000:0000:0000:0000:0000:0000:0001
Remote Port	Port for Remote HLR Router system used for auditing	Format: Digits only
Start Time/Completion Time	Date and time audit started and completed	Format: Time notation
State	Current state of the Remote audit	Format: Alpha <ul style="list-style-type: none"> <li>• Submitted</li> <li>• Queued</li> <li>• In Progress</li> <li>• Aborting</li> <li>• Aborted</li> <li>• Failed</li> <li>• Completed</li> </ul>
Audited	Total number of records audited	Format: Digits
Same	Number of matched records on both SDS and the Remote HLR Router system	Format: Digits
Diff	Number of mismatched records between SDS and Remote HLR Router system	Format: Digits
Missing	Number of SDS records that are missing on the Remote HLR Router system	Format: Digits
Extra	Number of HLR Router records that are missing on the local SDS system.	Format: Digits
Unknown	Number of records in SDS and/or HLR Router on which a retrieve data command timed out	Format: Digits
Errors	Number of errors that occurred during the audit. See trace log for more information	Format: Digits
Report	Name of generated remote audit report	Format: Alphanumeric

### Viewing the status of a remote audit

The **SDS > Maintenance > Remote Audit** page allows you to view all pending, completed, and failed remote database audits of data performed throughout the system.

1. Select **SDS > Maintenance > Remote Audit**.  
The **SDS Maintenance Remote Audit** page appears with all pending, completed, and failed remote database audits of data performed throughout the system displayed as a table. Click on any column heading to reorder the rows.
2. To look for a specific audit, click **Filter**.
3. Select the category to perform the filtering.  
The fields are described in [Remote audit elements](#).
4. Choose the filtering operator.

**Table 36: Remote Audit Filtering Operators**

Operator	Description
=	Is equal to
!=	Is not equal to
>	Is greater than
>=	Is equal to or greater than
<	Is less than
<=	Is equal to or less than
Like	Is Like (wildcard is * character)
Is Null	Has no entry (is zero)

5. Enter the target character string to filter on in the text box.
6. Click **Go** to show results.

### Requesting a remote audit

You can use this task to request a site-wide remote database audit of a specified subset of MSISDN, IMSI, NAI User or Wildcard NAI User data. The request is sent to all nodes and the results are merged back up to SDS. Because each node is responsible for managing its own resources, some nodes might decide to delay or cancel the requested audit in order to maintain sufficient resources to process signaling traffic.

**Note:** A valid input file name can be up to 80 characters in length.

1. Select **SDS > Maintenance > Remote Audit**.  
The **SDS Maintenance Remote Audit** page appears.
2. Click **Insert** located on the bottom of the page.  
The **SDS Maintenance Remote Audit [Insert]** page appears.
3. Select the type of data you want included in the audit from the **Data Type** pulldown list.

4. Select Range for **Audit By**, enter data in the following fields:
  - **Start of Range** field: Starting address of data to be included in this audit. This must be between 8 and 15 digits for MSISDN or 10-15 for IMSI.
  - **End of Range** field: Ending address of data to be included in this audit. This is an optional field that, if used, must be between 8 and 15 digits for MSISDN or 10-15 for IMSI.

Or, select File for **Audit By** and browse to the file containing ranges of values to be included in this audit.
5. Enter any text about the audit you want to include in the **Comment** field, if needed.
6. Perform one of these actions.
  - Click **OK**. If field validations succeed, the database audit request is made. The status of the request can be viewed on the **SDS > Maintenance > Remote Audit** page. If the page contains any values that are not valid, or if a required field is empty, an error message appears.
  - Click **Cancel** to abort changes on this page and return to the previous page.

## Query

The **SDS Maintenance Query** page allows you to query database information for a single provisioning database entry, or for a range of the same type of provisioning database entries, on an available server. Any server hosting a copy of the provisioning database can be used. Query options include MSISDN, IMSI, Destination, NAI Host, NAI User, Wildcard NAI User, Counts, Counts by Destination, and DB Level.

Querying a server for provisioning data allows you to see if data is being replicated correctly to each server, and allows you to see if adjustments to data management or to the subscriber database need to be made.

## Query elements

The **SDS Maintenance Query** page consists of query entry dialogue boxes and results display. Not all elements of the entry dialogue boxes or query results may be used once the Data type is selected. All elements available through Query entry dialogue boxes are presented in [Table 37: Query Entry Elements](#). All elements available through Query results display, in alphabetical order, are presented in [Table 38: Query Results Elements](#).

**Table 37: Query Entry Elements**

Element	Description	Data Input Notes
Data	Type of data to include in query	Format: Drop down list  Range: MSISDN, IMSI, MSISDN Prefix, IMSI Prefix, MSISDN Blacklist, IMSI Blacklist, NAI Host, NAI User, Wildcard NAI User, Destination, Counts, Counts by Destination, DB Level  Default: MSISDN

Element	Description	Data Input Notes
Start Address	Starting address of data to be included in this query (applies to MSISDN, IMSI, MSISDN Prefix, IMSI Prefix, MSISDN Blacklist and IMSI Blacklist query requests only)	Format: Digits only Range: 8 - 15 digits for MSISDN or MSISDN Blacklist, 10 - 15 for IMSI or IMSI Blacklist, 1 - 15 for MSISDN or IMSI Prefix
End Address	Ending address of data to be included in this query (applies to MSISDN, IMSI, MSISDN Prefix, IMSI Prefix, MSISDN Blacklist and IMSI Blacklist query requests only)	Format: Digits only Range: 8 - 15 digits for MSISDN or MSISDN Blacklist, 10 - 15 for IMSI or IMSI Blacklist, 1 - 15 for MSISDN or IMSI Prefix Default: blank
NAI Host	NAI Host to query applies to NAI users only	NAI Host defaults to the first one configured in the table.
Server	Server on which to run the query	Format: Alphanumeric Range: up to 35 characters Default: local server

**Table 38: Query Results Elements**

Result Element	Description	Data Value Selected
AAA	AAA Destination record (with type= aaa) or blank for none	MSISDN, IMSI, NAI User, Wildcard NAI User, MSISDN Prefix, IMSI Prefix
Destination(s)	Unique text used to identify a Destination	Counts, Counts by Destination
FQDN	A 1-255 character string for the Diameter FQDN for the Destination. The value can be null	Destination
Host	A unique string of 1 -64 characters for NAI Host Name	NAI User, Wildcard NAI User, NAI Host
IMSI(s)	A unique string of 10-15 decimal digits identifying the IMSI	IMSI, Counts, Counts by Destination
IMSI Blacklist	A unique string of 10-15 decimal digits identifying the IMSI Blacklist value	IMSI Blacklist, Counts
IMSI Prefix	A unique string of 1-15 decimal digits identifying the IMSI Prefix	IMSI Prefix, Counts, Counts by Destination
IMSHSS	IMS HSS Destination record (with type= imsHss) or blank for none	MSISDN, IMSI, NAI User, Wildcard NAI User, MSISDN Prefix, IMSI Prefix
LTEHSS	LTE HSS Destination record (with type= lteHss) or blank for none	MSISDN, IMSI, NAI User, Wildcard NAI User, MSISDN Prefix, IMSI Prefix

Result Element	Description	Data Value Selected
MSISDN(s)	A unique string of 8-15 decimal digits identifying the MSISDN	MSISDN, Counts, Counts by Destination
MSISDN Blacklist	A unique string of 8-15 decimal digits identifying the MSISDN Blacklist value	MSISDN Blacklist, Counts
MSISDN Prefix	A unique string of 1-15 decimal digits identifying the MSISDN Prefix	MSISDN Prefix, Counts, Counts by Destination
NAI Host	Number of NAI hosts	Counts
NAI User	A string of 1-64 characters for the NAI User Name	NAI User, Counts, Counts by Destination
Name	A unique string of 1-32 characters to identify the Destination	Destination
OCS	OCS Destination record (with type= ocs) or blank for none	MSISDN, IMSI, NAI User, Wildcard NAI User, MSISDN Prefix, IMSI Prefix
OfCS	OFCS Destination record (with type= ofcs) or blank for none	MSISDN, IMSI, NAI User, Wildcard NAI User, MSISDN Prefix, IMSI Prefix
PCRF	PCRF Destination record (with type= pcrf) or blank for none	MSISDN, IMSI, NAI User, Wildcard NAI User, MSISDN Prefix, IMSI Prefix
Realm	A 1-255 character string for the Diameter Realm for the Destination. The value can be null	Destination
Type	Destination type	Destination
USERDEF1	UserDef1 Destination record (with type= userDef1) or blank for none	MSISDN, IMSI, NAI User, Wildcard NAI User, MSISDN Prefix, IMSI Prefix
USERDEF2	UserDef2 Destination record (with type= userDef2) or blank for none	MSISDN, IMSI, NAI User, Wildcard NAI User, MSISDN Prefix, IMSI Prefix
Wildcard NAI User	A string of 1-64 characters for the wild carded NAI User Name.	Wildcard NAI User, Counts, Counts by Destination
DB Level	Numeric value of Database level	DB Level

**Running a query (MSISDN, IMSI, MSISDN Prefix, IMSI Prefix, MSISDN Blacklist, IMSI Blacklist)**

Use this task to query a single (or range of) MSISDN, IMSI, MSISDN Prefix, IMSI Prefix, MSISDN Blacklist, IMSI Blacklist values on any server within the system.

1. Select **SDS > Maintenance > Query**.  
The **SDS Maintenance Query** page appears.
2. Select a value from the **Data** pulldown list.
3. Enter the starting address of data to be included in this query in the **Start Address** field.

4. Enter the ending address of data to be included in this query in the **End Address** field.
5. Select the server you want to run the query on in the **Server** pulldown list.
6. Click **Query**.

The query is run and any relevant data is displayed on the page. See [Table 38: Query Results Elements](#).

### Running a query (NAI User)

You can use this task to query all of the NAI Users on any host and server within the server within the system.

1. Select **SDS > Maintenance > Query**.  
The **SDS Maintenance Query** page appears.
2. Select **NAI User** from the **Data** pulldown list.
3. Select the NAI Host to be included in this query in the **NAI Host** field.
4. Select the server you want to run the query on in the **Server** pulldown list.
5. Click **Query**.

The query is run and any relevant data is displayed on the page. See [Table 38: Query Results Elements](#).

### Running a query (Wildcard NAI User, NAI Host, Destination, Counts, Counts by Destination, or DB Level)

You can use this task to query all of the following:

- Wildcard NAI User
- NAI Host
- Destination
- Counts
- Counts by Destination Users on any server within the system

1. Select **SDS > Maintenance > Query**.  
The **SDS Maintenance Query** page appears.
2. Select one of the following from the **Data** pulldown list:
  - **Wildcard NAI User**
  - **NAI Host**
  - **Destination**
  - **Counts**
  - **Counts by Destination**
  - **DB Level**
3. Select the server you want to run the query on in the **Server** pulldown list.
4. Click **Query**.

The query is run and any relevant data is displayed on the page. See [Table 38: Query Results Elements](#).

## NPA Splits maintenance

Use this selection when you want to manage an NPA split in advance of a Permissive Dialing Period.

NPA Split refers to the telephone-numbering scheme that subdivides an old area code (old NPA) by the creation of a new area code (new NPA). This is necessary when the number of telephones in an old area code (old NPA) grows to an excessive number. As new area codes are defined (new NPA), some existing exchanges (NXX) may be assigned to the new area code (new NPA) from the old area code (old NPA).

The split is in the Pending state until it becomes Active on the Start date of the PDP. While in the Active state, Dialed Numbers (DN) in the split's NXX can use either the old NPA or the new NPA. After the split becomes complete on the End date of the PDP, only the new NPA can be used in a DN.

To manage NPA splits through the GUI, you must have group permission access to **NPA Splits** and **NPA Split Maintenance**.

## NPA Splits elements

Use the **SDS Maintenance NPA Splits** page to manage NPA splits. This table describes fields on this page.

**Table 39: NPA Splits Maintenance Elements**

Element	Description	Data Input Notes
Old NPA	The Numbering Plan Area the DNs will be split from. (Retrieve splits in which this NPA was the old NPA)	Format: Integer Range: 200 - 999, 3-digit number Default: blank
New NPA	The Numbering Plan Area the DNs will be split to. (Retrieve splits in which this NPA was the new NPA)	Format: Integer Range: 200 - 999, 3-digit number Default: blank
NXX	The exchange code value for this split. (Retrieve splits in which this NXX was the NXX.)  On the <b>Edit</b> and <b>Delete</b> pages, an <b>All</b> selection box is also available. If this check box is marked (the default) when the <b>OK</b> button is clicked, all NXXs are modified or deleted.	Format: Integer Range: 000 - 999, 3-digit number Default: blank
Start PDP Date	The start of the Permissive Dialing Period for this split. Grayed if NPA split is active.  <ul style="list-style-type: none"> <li>This date cannot be in the past, and must be before the PDP End date.</li> </ul>	Format: Pulldown menus Range: Valid date Default: Tomorrow's date

Element	Description	Data Input Notes
	<ul style="list-style-type: none"> <li>• Activation occurs within the first 15 minutes of the PDP Start date.</li> <li>• If today's date is entered, activation occurs within 15 minutes of the <b>Insert</b> or <b>Edit</b> button being clicked.</li> <li>• This field only appears on the <b>Insert</b> and <b>Edit</b> pages.</li> </ul>	
End PDP Date	<p>The end of the Permissive Dialing Period for this split.</p> <ul style="list-style-type: none"> <li>• This date cannot be in the past, and must be after the PDP Start date.</li> <li>• Termination occurs within the first 15 minutes of the PDP End date.</li> <li>• The date cannot be changed once the NPA split is complete.</li> <li>• This field only appears on the <b>Insert</b> and <b>Edit</b> pages.</li> </ul>	<p>Format: Pulldown menus</p> <p>Range: Valid date</p> <p>Default: Tomorrow's date + 90 days</p>

## Viewing NPA Splits

Use this task to display active or non-active NPA Split information.

If the **Save Results** checkbox is marked, the results are also saved to a CSV file named `NpaSplitReport.guiadmin.<timestamp>.csv`. This file can then be viewed and downloaded in the SDS file management area (**Status & Manage > Files**).

1. Select **SDS > Maintenance > NPA Splits**.  
The **SDS Maintenance NPA Splits** page appears with all NPA Split information found in the PDB database. Click on any column heading to reorder the rows.
2. To look for a specific NPA Split, click **Filter**.
3. Add search criteria to the fields in the **Value** column, as desired.
4. Mark or unmark any **All** checkboxes.
5. Click **Go** to show results.  
The **SDS Maintenance NPA Splits (Filtered)** page displays the results.

## Creating an NPA Split

Use this procedure to create an NPA split and define its characteristics, including the old NPA code, the new NPA code, the central office exchange (NXX) code(s) to be transferred to the new NPA, and the beginning and ending dates of the Permissive Dialing Period (PDP).

1. Select **SDS > Maintenance > NPA Splits**  
The **SDS Maintenance NPA Splits** page appears.
2. Click **Insert** located at the bottom of the page.  
The **SDS Maintenance NPA Splits [Insert]** page appears.

3. Enter data to provision an NPA split. Values must be entered for **Old NPA**, **New NPA**, and **NXX**. If dates are entered in the **PDP Start** and/or **PDP End** dates, these dates must be greater than today's date.  
For more information about these fields, see [NPA Splits elements](#).
4. Perform one of these actions:
  - Click **OK**. The NPA Split record is provisioned. Its state is initialized to Pending and the previous page appears. If the page contains any values that are not valid, or if a required field is empty, an error message appears.
  - Click **Apply**. If field validations succeed, the new export is saved and you remain on the same page.
  - Click **Cancel** to abort changes on this page and return to the previous page.

## Editing an NPA Split

Use this procedure to modify the start and/or end the Permissive Dialing Period (PDP) dates of one or more existing NPA splits.

1. Select **SDS > Maintenance > NPA Splits**.  
The **SDS Maintenance NPA Splits** page appears.
2. Highlight the NPA Split you want to edit and click **Edit**.  
The **SDS Maintenance NPA Splits [Edit]** page appears.
3. To modify all **NXX**, make sure the **All** checkbox is marked.
4. Enter the **PDP Start** and/or **PDP End** dates, as needed.  
Both the **PDP Start** and **PDP End** dates can be modified for pending splits. Only the **PDP End** date can be modified for active splits. Neither can be modified for completed splits. The **PDP End** date must be greater than today's date.  
For more information about these fields, see [NPA Splits elements](#).
5. Perform one of these actions:
  - Click **OK**. If field validations succeed, the NPA splits are updated. If the page contains any values that are not valid, an error message appears.
  - Click **Cancel** to abort changes on this page and return to the previous page.

## Deleting an NPA Split

Use this procedure to delete NPA Splits whose Permissive Dialing Period is pending or has expired.

1. Select **SDS > Maintenance > NPA Splits**.  
The **SDS Maintenance NPA Splits** page appears.
2. Highlight the NPA Split you want to delete and click **Delete**.  
A confirmation pop up window appears, asking if you are sure you want to delete this NPA Split.
3. Perform one of the following actions:
  - Click **OK** to confirm the action to delete NPA Split and return to the **SDS > Maintenance > NPA Splits** page.

- Click **Cancel** to abort the delete action and return to the **SDS > Maintenance > NPA Splits** page.

## A

AAA Authentication, Authorization, and Accounting (Rx Diameter command)

APDE Automated Performance Data Export

## C

CID Connection ID

## D

DP Data Processor  
The repository of subscriber data on the individual node elements. The DP hosts the full address resolution database.

DP SOAM Data Processor System Operations, Administration, and Maintenance

DR Disaster Recovery

## F

FABR Full Address Based Resolution  
Provides an enhanced DSR routing capability to enable network operators to resolve the designated Diameter server addresses based on individual user identity addresses in the incoming Diameter request messages.

FQDN Fully Qualified Domain Name

**F**

The complete domain name for a specific computer on the Internet (for example, www.oracle.com).

A domain name that specifies its exact location in the tree hierarchy of the DNS.

**G**

GUI

Graphical User Interface

The term given to that set of items and facilities which provides you with a graphic means for manipulating screen data rather than being limited to character based commands.

**H**

HA

High Availability

High Availability refers to a system or component that operates on a continuous basis by utilizing redundant connectivity, thereby circumventing unplanned outages.

HLRR

HLR Router

HSS

Home Subscriber Server

A central database for subscriber information.

HTTP

Hypertext Transfer Protocol

**I**

IETF

Internet Engineering Task Force

The Internet Engineering Task Force is an open international community of network designers, professional users, and manufacturers who promote the

**I**

development and operations of the Internet.

**IMS**

IP Multimedia Subsystem

These are central integration platforms for controlling mobile communications services, customer management and accounting for mobile communications services based on IP. The IMS concept is supported by 3GPP and the UMTS Forum and is designed to provide a wide range of application scenarios for individual and group communication.

**IP**

Internet Protocol - IP specifies the format of packets, also called datagrams, and the addressing scheme. The network layer for the TCP/IP protocol suite widely used on Ethernet networks, defined in STD 5, RFC 791. IP is a connectionless, best-effort packet switching protocol. It provides packet routing, fragmentation and re-assembly through the data link layer.

**L****LTE**

Long Term Evolution

The next-generation network beyond 3G. In addition to enabling fixed to mobile migrations of Internet applications such as Voice over IP (VoIP), video streaming, music downloading, mobile TV, and many others, LTE networks will also provide the capacity to support an explosion in demand for connectivity from a new generation of consumer devices tailored to those new mobile applications.

**N**

NE

Network Element

An independent and identifiable piece of equipment closely associated with at least one processor, and within a single location.

In a 2-Tiered DSR OAM system, this includes the NOAM and all MPs underneath it. In a 3-Tiered DSR OAM system, this includes the NOAM, the SOAM, and all MPs associated with the SOAM.

The devices, servers, or functions within a wireless network with which Policy Management systems interact.

NPA

Number Plan Area

The North American "Area Codes." (3 digits: 2- to-9, 0 or 1, 0-to-9. Middle digit to expand soon).

NXX

Central Office Exchange Code

**O**

OCS

Online Charging System

A system allowing a Communications Service Provider to charge customers in real time based on service usage.

**P**

PCRF

Policy and Charging Rules Function

The ability to dynamically control access, services, network capacity, and charges in a network.

Maintains rules regarding a subscriber's use of network

**P**

resources. Responds to CCR and AAR messages. Periodically sends RAR messages. All policy sessions for a given subscriber, originating anywhere in the network, must be processed by the same PCRF.

In the Policy Management system, PCRF is located in the MPE device.

Software node designated in real-time to determine policy rules in a multimedia network.

PDP

Permissive Dialing Period

**S**

SDS

Subscriber Database Server

Subscriber Database Server (SDS) provides the central provisioning of the Full-Address Based Resolution (FABR) data. The SDS, which is deployed geo-redundantly at a Primary and Disaster recovery site, connects with the Query Server and the Data Processor System Operations, Administration, and Maintenance ( DP SOAM) servers at each Diameter Signaling Router (DSR) site or a standalone DP site to replicate and recover provisioned data to the associated components.

SNMP

Simple Network Management Protocol.

An industry-wide standard protocol used for network management. The SNMP agent maintains data variables that represent aspects of the network. These variables are called managed objects and are stored in a management information base (MIB). The SNMP protocol

**S**

arranges managed objects into groups.

SOAM

System Operations,  
Administration, and Maintenance

SQL

Structured Query Language  
A special programming language for querying and managing databases.

**T**

TCP

Transmission Control Protocol  
A connection-oriented protocol used by applications on networked hosts to connect to one another and to exchange streams of data in a reliable and in-order manner.

**X**

XML

eXtensible Markup Language  
A version of the Standard Generalized Markup Language (SGML) that allows Web developers to create customized tags for additional functionality.