

Siebel CRM
System Administration Guide
Siebel Innovation Pack 2017
E24823-01

November 2017

Copyright © 2005, 2017 Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

This documentation is in preproduction status and is intended for demonstration and preliminary use only. It may not be specific to the hardware on which you are using the software. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to this documentation and will not be responsible for any loss, costs, or damages incurred due to the use of this documentation.

The information contained in this document is for informational sharing purposes only and should be considered in your capacity as a customer advisory board member or pursuant to your beta trial agreement only. It is not a commitment to deliver any material, code, or functionality, and should not be relied upon in making purchasing decisions. The development, release, and timing of any features or functionality described in this document remains at the sole discretion of Oracle.

This document in any form, software or printed matter, contains proprietary information that is the exclusive property of Oracle. Your access to and use of this confidential material is subject to the terms and conditions of your Oracle Master Agreement, Oracle License and Services Agreement, Oracle PartnerNetwork Agreement, Oracle distribution agreement, or other license agreement which has been executed by you and Oracle and with which you agree to comply. This document and information contained herein may not be disclosed, copied, reproduced, or distributed to anyone outside Oracle without prior written consent of Oracle. This document is not part of your license agreement nor can it be incorporated into any contractual agreement with Oracle or its subsidiaries or affiliates.

Contents

Preface	ix
Audience	ix
Documentation Accessibility	ix
Related Documents	ix
Conventions	x
1 What's New in This Release	
What's New in <i>Siebel System Administration Guide, Siebel Innovation Pack 2017</i>	1-1
What's New in <i>Siebel System Administration Guide, Siebel Innovation Pack 2016</i>	1-2
2 Siebel Enterprise Server Architecture	
About the Siebel Environment	2-1
About the Siebel Gateway	2-2
Impact of Failure	2-3
About the Siebel Enterprise Server	2-3
About the Siebel Server	2-3
About the Siebel Server System Service	2-4
About Siebel Server Manager	2-5
About Siebel Server Components	2-6
About Server Component Modes	2-6
About Server Component Types	2-7
About Server Component Groups	2-7
About Server Component Processes (Shells)	2-8
About the Siebel Application Interface	2-9
About the Siebel File System and the File System Manager	2-10
About the Siebel Management Pack	2-10
3 Configuring the System Architecture	
About Configuring the Siebel Server and Its Components	3-1
About System Environment Variables	3-2
Configuring System Environment Variables	3-4
Configuring an Environment Variable on Windows	3-4
Configuring an Environment Variable on UNIX	3-4
Configuring Siebel Server Load Balancing	3-5
Rebalancing Siebel Server Loads	3-5

Troubleshooting Siebel Native Load Balancing	3-5
Verifying Load Balancing Port Access on Siebel Servers	3-6
Configuring the Session Manager	3-7
Reinstalling the Siebel Gateway and Siebel Server	3-8

4 Configuring Siebel Servers

About the Server Manager GUI	4-1
About the Enterprise Explorer View	4-2
About the Process Failure Diagnostics View	4-2
About Siebel System Parameters	4-2
About Advanced and Hidden Parameters	4-4
About Parameter Availability Status	4-4
About Siebel Enterprise Server Parameters	4-4
About Siebel Server Parameters	4-5
About Siebel Component Parameters	4-5
About Task Parameters	4-6
About Named Subsystem Parameters	4-6
Configuring the Siebel Enterprise Server	4-7
About Assigned and Unassigned Component Groups	4-8
Unassigning Component Groups on a Siebel Server	4-8
Assigning Component Groups on a Siebel Server	4-9
About Enabled and Disabled Component Groups	4-10
Enabling Component Groups on a Siebel Enterprise Server	4-11
Disabling Component Groups on a Siebel Enterprise Server	4-11
Configuring Siebel Enterprise Server Named Subsystem Parameters	4-11
Creating Siebel Enterprise Server Named Subsystems	4-12
Configuring Siebel Enterprise Parameters	4-13
Configuring Siebel Enterprise Component Definition Parameters	4-13
About System Alert Notification	4-14
Configuring System Alert Notification	4-14
Troubleshooting System Alert Notification	4-16
Configuring Component Job Templates	4-16
Synchronizing Components on a Siebel Enterprise Server	4-17
Configuring the Siebel Server	4-18
Enabling Component Groups on a Siebel Server	4-18
Disabling Component Groups on a Siebel Server	4-19
About Starting Siebel Server Components	4-19
Automatically Starting a Component on a Siebel Server	4-20
Manually Starting or Disabling a Component on a Siebel Server	4-21
Configuring Siebel Server Parameters	4-21
Configuring Siebel Server Component Parameters	4-21
Checking Your Siebel Enterprise and Siebel Server Configurations	4-22
About Siebel Server Component Definitions	4-22
Process of Creating a Custom Siebel Server Component	4-23
Creating a Custom Siebel Server Component Group	4-24
Creating a Custom Siebel Server Component Definition	4-24
Activating a Custom Siebel Server Component Definition	4-25

Deleting a Siebel Server Component Definition	4-26
Deactivating a Siebel Server Component Definition	4-26
Advanced Configuration Tasks	4-27
Reconfiguring Siebel Server Component Definitions	4-27
Configuring Automatic Restart for Server Components	4-29
Configuring Database Reconnect for Server Components	4-29
Configuring Memory-Based Server Component Recycling	4-30
Deleting System Parameter Overrides	4-31

5 Administering Server System Services

Starting and Shutting Down a Siebel CRM Deployment.....	5-1
Starting a Siebel CRM Deployment.....	5-1
Shutting Down a Siebel CRM Deployment.....	5-2
Administering the Siebel Gateway System Service.....	5-3
About Siebel Gateway Authentication.....	5-3
Administering the Siebel Gateway System Service on Windows.....	5-4
Administering the Siebel Gateway System Service on UNIX	5-5
Administering the Siebel Server System Service	5-7
Administering the Siebel Server System Service on Windows	5-7
Administering the Siebel Server System Service on UNIX.....	5-9

6 Administering Siebel Server Run-Time Operations

Administering Siebel Servers.....	6-1
Starting a Siebel Server.....	6-1
Shutting Down a Siebel Server.....	6-2
Administering Siebel Server Component Groups	6-2
Enabling a Component Group on a Siebel Server	6-3
Disabling a Component Group on a Siebel Server.....	6-3
Administering Siebel Server Components	6-3
Starting a Server Component on a Siebel Server	6-4
Shutting Down a Server Component on a Siebel Server.....	6-4
Recovering an Unavailable Server Component.....	6-4
Pausing Server Components on a Siebel Server	6-5
Resuming Server Components on a Siebel Server	6-5
Administering Component Jobs	6-5
About Component Jobs.....	6-6
Starting a Component Job.....	6-6
Starting a Repeating Component Job.....	6-8
Deleting a Component Job or Repeating Component Job	6-9
Canceling a Component Job or Repeating Component Job.....	6-9
Holding a Component Job or Repeating Component Job.....	6-10
Resuming a Component Job or Repeating Component Job.....	6-10
Troubleshooting Component Jobs.....	6-10
Administering Siebel Server Tasks.....	6-11
Starting a Siebel Server Task	6-11
Pausing a Siebel Server Task	6-11

Resuming a Siebel Server Task.....	6-12
Stopping a Siebel Server Task	6-12
Terminating a Siebel Server Task	6-13
Configuring Siebel Server Task Dynamic Parameters.....	6-13

7 Using the Siebel Server Manager Command-Line Interface

Starting the Siebel Server Manager Command-Line Interface	7-1
Starting the Siebel Server Manager Program	7-1
Command-Line Flags for the Siebel Server Manager Program	7-2
About Error Handling for the Siebel Server Manager Program	7-3
Recommendations for Using the Command-Line Interface	7-4
Siebel Server Manager Commands	7-5
Command Syntax	7-6
Help Commands	7-7
Siebel Server Manager Environment Commands	7-7
List Commands	7-8
List Command Configuration	7-12
Server Group Management Commands	7-12
Siebel Server Management Commands	7-13
Component Group Definition Commands	7-13
Component Definition Commands	7-15
Reconfiguring Component Definition Commands	7-16
Component Management Commands	7-17
Task Management Commands	7-18
Parameter Management Commands	7-20
Named Subsystem Management Commands	7-21
System Alert Notification Commands	7-22
List Definition Commands	7-22
List Parameter Override Commands	7-22
Event Logging Commands	7-23
Server Manager Command-Line Preferences	7-24

8 Siebel Server Infrastructure Administration

About Server Request Broker (SRBroker)	8-1
Configuring Tasks for Server Request Broker	8-2
About Server Request Processor (SRProc)	8-2
About Siebel Connection Broker (SCBroker)	8-3
About Other System Management Components	8-3
About Server Tables Cleanup (SvrTblCleanup)	8-4
About Siebel Administrator Notification (AdminNotify)	8-4
About Siebel Server Scheduler (SvrSched)	8-4
Administering the Siebel File System	8-5
About the Siebel File System	8-5
About the File System Upload and Download Process	8-6
About the File System Upload Transfer Process	8-6
About the File System Download Transfer Process	8-6
Partitioning the Siebel File System	8-7

Cleaning Up the Siebel File System	8-10
--	------

9 Application Object Manager Administration

About the Siebel Application Object Manager	9-1
About Application Object Manager Memory Allocation	9-2
Configuring the Application Object Manager Environment	9-2
About Application Object Manager Parameters	9-3
Application Object Manager Parameters in Server Manager	9-3
Application Object Manager Named Subsystem Parameters	9-4
Administering the Application Object Manager	9-6

A Siebel Server Components and Parameters

Siebel Server Component Groups	A-1
Siebel Server Components	A-4
Siebel Enterprise, Server, and Component Parameters	A-11
Siebel Enterprise Server Parameters	A-15
Siebel Server Parameters	A-16
Generic Parameters	A-18

B Parameters in Siebel Application Configuration Files

Overview of Parameters in Siebel Application Configuration Files	B-1
About Siebel Application Configuration Files	B-2
Editing Siebel Application Configuration Files	B-3
Configuration Parameters Index	B-4
Description of Siebel Application Parameters	B-9
Data Source Parameters	B-11
Parameters for DataSources Section	B-11
Parameters for Individual Data Source Sections	B-12

Index

List of Tables

1-1	What's New in <i>Siebel System Administration Guide</i> , Siebel Innovation Pack 2017.....	1-1
1-2	What's New in <i>Siebel System Administration Guide</i> , Siebel Innovation Pack 2016.....	1-2
2-1	Siebel Application Entities.....	2-1
2-2	Shell Types for Interactive-Mode Components.....	2-8
2-3	Shell Types for Batch-Mode Components.....	2-9
2-4	Shell Types for Background-Mode Components.....	2-9
3-1	Partial Listing of Siebel Environment Variables.....	3-2
3-2	Resolving Siebel Native Load Balancing Problems.....	3-6
4-1	Hierarchy of System Parameters.....	4-3
4-2	Parameter Availability Status Options.....	4-4
4-3	Resolving System Alert Notification Problems.....	4-16
6-1	Resolving Component Job Problems.....	6-11
6-2	Pausable Component Types.....	6-11
7-1	Example Parameters for Starting the <code>svrmgr</code> Program.....	7-2
7-2	Command-Line Flags for <code>svrmgr</code>	7-2
8-1	Parameters for <code>sfspartition</code> Utility.....	8-10
8-2	Parameters for <code>sfscleanup</code> Utility.....	8-11
8-3	File Types and Associated Operations for <code>sfscleanup</code> Utility.....	8-14
8-4	Operations for <code>sfscleanup</code> Utility.....	8-14
9-1	Named Subsystems Used by Application Object Managers.....	9-4
9-2	Named Subsystem Parameters.....	9-5
A-1	Predefined Siebel Server Component Groups.....	A-1
A-2	Predefined Siebel Server Components.....	A-5
A-3	Parameters and Attributes.....	A-12
A-4	Values for <code>ConnIdleTime</code> Parameter.....	A-24
B-1	Some Siebel Business Applications and Associated Configuration Files.....	B-2
B-2	Index of Configuration Parameters.....	B-4
B-3	Siebel Application Parameters.....	B-9
B-4	Data Sources.....	B-11
B-5	Data Source Parameters.....	B-12

Preface

This guide covers tasks for administering Siebel Business Applications.

Audience

This guide is intended for system administrators.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at

<http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit

<http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit

<http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit

<http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit

<http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Related Documents

For more information, see the following documents on Oracle Technology Network:

- *Siebel Deployment Planning Guide*
- *Siebel Installation Guide for the operating system you are using*
- *Deploying Siebel Open UI*
- *Siebel Security Guide*
- *Siebel System Monitoring and Diagnostics Guide*
- *Siebel Performance Tuning Guide*
- *Siebel Applications Administration Guide*

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, a defined term, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, code in examples, text that appears on the screen, or text that you enter.

What's New in This Release

Siebel System Administration Guide provides information about performing server administration tasks for Oracle's Siebel Business Applications.

What's New in *Siebel System Administration Guide*, Siebel Innovation Pack 2017

[Table 1–1](#) lists the changes in this revision of the documentation to support this release of the software.

Table 1–1 *What's New in Siebel System Administration Guide, Siebel Innovation Pack 2017*

Topic	Description
Multiple topics	Modified topics. In the current release, the Siebel Gateway Name Server has been replaced by a new module called Siebel Gateway. The Siebel Web Server Extension (SWSE) has been replaced by a new module, Siebel Application Interface.
Multiple topics	Modified topics. In the current release, the Siebel Runtime Repository replaces the Siebel Repository File (SRF).
"Starting and Shutting Down a Siebel CRM Deployment" on page 5-1	Modified topic. Added information about starting and stopping the application container.
"Migrating Parameters Between Environments"	Removed appendix. The <code>cfgmerge</code> utility is no longer supported.
"Siebel Server Component Groups" on page A-1 "Siebel Server Components" on page A-4	Modified topics. Removed the Siebel Rest Proxy Object Manager (alias <code>SiebelRestCompIntMgr</code>), a component that had been added to the EAI component group for Siebel Innovation Pack 2016. Also removed the Siebel Core Reference Application component group (alias CRA).
"Siebel Enterprise, Server, and Component Parameters" on page A-11	Modified topic. Updated the server parameter coverage, as follows: <ul style="list-style-type: none"> ■ Removed the obsolete parameter <code>DfltProcs</code>. ■ Removed the obsolete parameter <code>EnableComposer</code>. The functionality previously enabled using this parameter is now in effect by default and cannot be changed. For more information, see <i>Using Siebel Tools</i>.

Table 1–1 (Cont.) What's New in Siebel System Administration Guide, Siebel Innovation Pack 2017

Topic	Description
"Structure of the eapps.cfg File"	Removed appendix. In the current release, the Siebel Application Interface has replaced the Siebel Web Server Extension, and the eapps.cfg file no longer applies. For information about the Siebel Application Interface settings available in the Siebel Management Console, see the <i>Siebel Installation Guide</i> for the operating system you are using.
"Configuration Parameters Index" on page B-4	Modified topic. Updated the configuration parameter coverage, as follows: <ul style="list-style-type: none"> Removed the obsolete parameter CalDAVService, from the [HTTP Services] section of the eai.cfg file. Removed the obsolete parameters Method and Service, from the [CalDAVService] section of the eai.cfg file.
"Structure of the lbconfig.txt File"	Removed appendix. Load balancing as configured in previous releases no longer applies. Siebel native load balancing is supported in the current release, and works differently than in previous releases. For more information, see the <i>Siebel Installation Guide</i> for the operating system you are using.

What's New in *Siebel System Administration Guide*, Siebel Innovation Pack 2016

Table 1–2 lists the changes in this revision of the documentation to support this release of the software.

Table 1–2 What's New in Siebel System Administration Guide, Siebel Innovation Pack 2016

Topic	Description
"Configuring the Browser for Siebel Web Clients" (removed) Multiple topics (modified)	Removed chapter. Removed this chapter, most of which related to browser configuration requirements for the high interactivity client or the standard interactivity client, which are no longer supported. Also updated various topics to remove references to these clients or for related updates. Moved information from the following topics into the <i>Siebel Installation Guide</i> for the operating system you are using: <ul style="list-style-type: none"> "Siebel Client Deployment Requirements When Using Firewalls or Proxy Servers" "Configuring Siebel Business Applications for Pop-Up Blocker Compatibility"
Multiple topics	Modified topics. Removed references to the Siebel Wireless or Siebel Handheld applications, which are no longer provided.

Table 1–2 (Cont.) What's New in Siebel System Administration Guide, Siebel Innovation Pack 2016

Topic	Description
<p>"Siebel Server Component Groups" on page A-1</p> <p>"Siebel Server Components" on page A-4</p>	<p>Modified topics.</p> <p>Added the Siebel Rest Proxy Object Manager (SiebelRestCompIntMgr), a new component in the EAI component group. (This component is obsolete in Siebel Innovation Pack 2017.)</p> <p>Removed components for Siebel Store-and-Forward Messaging, Siebel Mobile Connector, Siebel Wireless, and Siebel Handheld applications; and other components that do not support Siebel Open UI, as follows:</p> <ul style="list-style-type: none"> ■ Removed the component group MWC Real Time Sync (RTSRemote) and all of its components. ■ Removed the component SMQ Receiver (SMQReceiver) from the EAI component group. ■ Removed the component Siebel Mobile Connector Object Manager (SMCObjMgr) from the Sales component group. ■ Removed the component group Siebel Wireless (Wireless) and all of its components. ■ Removed the Object Manager components for Siebel Handheld from the component groups HandheldSync and HandheldSyncSIS. ■ Removed the component eService Object Manager (eServiceObjMgr) from the CallCenter component group.
<p>"Siebel Enterprise, Server, and Component Parameters" on page A-11</p>	<p>Modified topic. Revised several server parameters and removed several obsolete server parameters, many of which applied only to high interactivity or standard interactivity, as follows:</p> <ul style="list-style-type: none"> ■ Added the parameter EnableComposer. This parameter replaces the obsolete parameter EnableResponsive. (This parameter is obsolete in Siebel Innovation Pack 2017.) ■ Removed the obsolete parameters EnableCDA, EnableEmailClientAutomation, EnableOpenUI, EnableResponsive, EnableSIBusyCursor, EnableSIDataLossWarning, EnableWebClientAutomation, HighInteractivity, JREDownloadUrl, ListRowStyle, MarkupLanguage, and SiebEntSecToken.
<p>"Parameter Descriptions of the eapps.cfg File" (removed in Siebel Innovation Pack 2017)</p>	<p>Modified topic.</p> <ul style="list-style-type: none"> ■ Revised the description of the SessionTracking parameter in the [defaults] section of the eapps.cfg file. The URLSession and CookieSession parameters are also affected. ■ Added the parameters SessionTimeoutWLCCommand and SessionTimeoutWLMMethod to the [defaults] section. <p>Note: In Siebel Innovation Pack 2017, the Siebel Application Interface has replaced the Siebel Web Server Extension, and the eapps.cfg file no longer applies. For information about the Siebel Application Interface settings available in the Siebel Management Console, see the <i>Siebel Installation Guide</i> for the operating system you are using.</p>

Table 1–2 (Cont.) What's New in Siebel System Administration Guide, Siebel Innovation Pack 2016

Topic	Description
"Configuration Parameters Index" on page B-4	Modified topic. Many of these parameters also function as server parameters, but are not documented as such. <ul style="list-style-type: none"> ■ Removed the parameter DefaultChartFont from the [Siebel] section. ■ Removed the parameter EnableResponsive from the [InfraUIFramework] section. ■ Removed the parameter ExtendedKeyboard from the [InfraUIFramework] section. ■ Removed the parameters LotusForm and OutlookForm from the [Email] section. ■ Removed the parameter ViewPreloadSize from the [InfraUIFramework] section and all of the parameters in the [Preload] section.
"Data Source Parameters" on page B-11	Modified topic. <ul style="list-style-type: none"> ■ Removed the AutoStartDB parameter, which is no longer applicable. ■ Updated the description of the ConnectString parameter. ■ Updated the description of the FileSystem parameter. ■ Removed the SortCollation parameter. ■ Updated the description of the SqlStyle parameter.

Siebel Enterprise Server Architecture

This chapter provides an overview of Oracle's Siebel Enterprise Server architecture. This chapter includes the following topics:

- [About the Siebel Environment](#)
- [About the Siebel Gateway](#)
- [About the Siebel Enterprise Server](#)
- [About the Siebel Server](#)
- [About Siebel Server Components](#)
- [About the Siebel Application Interface](#)
- [About the Siebel File System and the File System Manager](#)
- [About the Siebel Management Pack](#)

About the Siebel Environment

Each Siebel Business Applications environment includes at least the following entities, listed in [Table 2-1](#).

Table 2-1 Siebel Application Entities

Entity	Comments
Siebel clients	Client types include Siebel Web Client, Siebel Mobile Web Client, Siebel Developer Web Client, and Siebel Mobile applications. The Siebel Tools client is a special-purpose client for developers.
Siebel Gateway	A module that provides persistent and dynamic storage of configuration information for the Siebel Enterprise, Siebel Server, Siebel Application Interface, and other configurable entities.
Siebel Enterprise Server	The logical grouping of one or more Siebel Servers in your deployment. You must configure the Siebel Enterprise before you can configure the Siebel Server.
Siebel Server	The middle-tier platform that supports both back-end and interactive processes for every Siebel client. Siebel Server includes many different types of components, including Siebel Application Object Managers.
Siebel Application Interface	A module that enables communication between Siebel Web Clients and Siebel Servers.

Table 2–1 (Cont.) Siebel Application Entities

Entity	Comments
Siebel database	The Siebel tables, indexes, and seed data installed on the RDBMS. Database client software is also required.
Siebel File System	One or more directories that store physical files used by Siebel clients and Siebel Enterprise Server.

The Siebel Enterprise Server environment represents the middle tier within the three-tiered Siebel Business Applications environment, between the Siebel client and the Siebel database. For more information, see *Siebel Deployment Planning Guide*. For installation information, see the *Siebel Installation Guide* for the operating system you are using.

About the Siebel Gateway

The Siebel Gateway coordinates the Siebel Enterprise Server and Siebel Servers. A single Siebel Gateway can support a single Siebel Enterprise Server. The Siebel Gateway provides the persistent backing of Siebel Enterprise Server configuration information, including:

- Definitions and assignments of component groups and components
- Operational parameters
- Connectivity information

Because this information changes, such as during the configuration of a Siebel Server, it is written to the Siebel Gateway registry. At startup, the Siebel Server obtains its configuration information from the Siebel Gateway registry.

The Siebel Gateway provides the dynamic registry for Siebel Server and component availability information. At startup, a Siebel Server within the Siebel Enterprise Server notifies the Siebel Gateway of its availability and stores its connectivity information, such as network addresses, in the Siebel Gateway's nonpersistent (volatile) store.

Enterprise components (including the Server Manager) query the Siebel Gateway for Siebel Server availability and connectivity information. When a Siebel Server shuts down, this nonpersistent information is cleared from the Siebel Gateway.

In a Windows environment, the Siebel Gateway runs as a Windows service. In a UNIX environment, the Siebel Gateway runs as a daemon process. The system process for the Siebel Gateway is `siebsvc.exe` on Windows and `siebsvc` on UNIX. Each running Siebel Server has a corresponding Siebel Gateway system process.

The Siebel Gateway also includes an application container. The application container process for the Siebel Gateway is `javaw.exe` on Windows and `javaw` on UNIX.

A single Siebel Gateway can potentially serve several databases in an environment (such as multiple development and test environments). To mitigate dependencies and improve recoverability, keep the Siebel production environment separate from other Siebel environments (development or test) by using a separate Siebel Gateway.

If you decide to maintain multiple development or test environments on one Siebel Gateway, then you must use a distinct Siebel Enterprise Server for each table owner (or each Siebel database, for Microsoft SQL Server).

Note: There can be only one Siebel Gateway installed on any one computer. For more information, see *Siebel Deployment Planning Guide* and the *Siebel Installation Guide* for the operating system you are using.

Impact of Failure

When the Siebel Gateway goes down, service to active user connections is not immediately interrupted. All of the Siebel Server components, including Application Object Managers, that are currently running continue to do so. However, no new Siebel Server components can be started or added. Server administration functions become limited.

About the Siebel Enterprise Server

The Siebel Enterprise Server is a logical grouping of Siebel Servers that supports a group of users accessing a common Siebel database. The Siebel Enterprise Server can be configured, managed, and monitored as a single logical group, allowing the Siebel administrator to start, stop, monitor, or set parameters for Siebel Servers within a Siebel Enterprise Server. You must configure the Siebel Enterprise before you can configure the Siebel Server.

You can set some Siebel Server parameters at the Siebel Enterprise Server level, and these parameters apply to every Siebel Server and component operating within that Siebel Enterprise Server. Other parameters can be adjusted at the Siebel Server or component level to support fine-tuning your deployment.

Parameter settings are inherited unless overrides are in effect, as follows:

- If a parameter is set at the server level, then the server-specific value overrides the Siebel Enterprise Server parameter setting on that server.
- If a parameter is set at the component level, then the component-specific value overrides the enterprise-level or server-level parameter setting on that component.

Each Siebel Server belonging to a Siebel Enterprise Server must connect to the same Siebel database in the same database server.

The Siebel Enterprise Server itself has no processes and, therefore, cannot have a state.

For more information about configuring the Siebel Enterprise Server, see "[Configuring the Siebel Enterprise Server](#)" on page 4-7.

About the Siebel Server

The Siebel Server is the middle-tier platform that supports both back-end and interactive processes for every Siebel client. These processes are components within the Siebel Server architecture and support functions like the following:

- Operation of business logic for Siebel Web clients, as well as connectivity and access to the Siebel database and Siebel File System
- Mobile Web Client synchronization
- Integration with legacy or third-party data
- Automatic assignment of new accounts, opportunities, service requests, and other records
- Workflow management

The Siebel Server supports both multiprocess and multithreaded components, and can operate components in background, batch, and interactive modes. Many of the Siebel Server components can operate on multiple Siebel Servers simultaneously to support an increased number of users or larger batch workloads. For more information about Siebel Server components, see ["About Siebel Server Components"](#) on page 2-6.

Note: Make sure that your server hardware and software meet minimum standards. For more information, see the Certifications tab on My Oracle Support.

About the Siebel Server System Service

The Siebel Server runs as a system service that monitors and controls the state of every Siebel Server component operating on that Siebel Server. Each Siebel Server is an instantiation of the Siebel Server system service within the current Siebel Enterprise Server.

The Siebel Server runs as a Windows service in a Windows environment and a daemon process in a UNIX environment. The system process associated with the Siebel Server is `siebsvc.exe` on Windows and `siebsvc` on UNIX. Each running Siebel Server has a corresponding Siebel Server system process. For information about administering the Siebel Server system service, see ["Administering the Siebel Server System Service"](#) on page 5-7.

During startup, the Siebel Server system service performs the following sequential steps:

- Retrieves configuration information from the Siebel Gateway. For information about the Siebel Gateway, see ["About the Siebel Gateway"](#) on page 2-2.
- Creates a shared memory file located in the `admin` subdirectory of the Siebel Server root directory on Windows and the `sys` subdirectory on UNIX. By default, this file has the following name:

Enterprise_Server_Name.Siebel_Server_Name.shm

The total shared memory consists of a fixed amount for the Siebel Server itself, a block for each server component running on the server, and a block for each task.

Prior to creating the SHM file, the shared memory for the Siebel application executables is built up in the RAM of the computer by using the information retrieved from the Siebel Gateway. This process can use significant amounts of memory. After the creation of the SHM file, the Siebel Server system service releases this memory. The Siebel Server system service deletes this file when it shuts down.

Note: If the Siebel Server system service is improperly shut down, then the SHM file might not be deleted by the Siebel Server system service. In this case, delete (or rename) this file before restarting the Siebel Server system service. If this file is not visible, then it might be a hidden file.

- Siebel Connection Broker (alias SCBroker) server component opens a TCP port to accept inbound Application Object Manager requests. If there are multiple instances of SCBroker on this Siebel Server, then all of the instances listen on the same port.

- Opens TCP ports dynamically for non-Application Object Manager components as necessary, such as Workflow Process Manager.
- Forks single-threaded and multithreaded processes for background mode components enabled on the Siebel Server. The previously created ports are inherited to these processes. For more information about these processes, see "[About Server Component Processes \(Shells\)](#)" on page 2-8.
- When server component processes start, each process updates the shared memory table with component availability and status information. SCBroker and SRBroker use this information for load balancing and routing purposes.
- Archives log files by moving the current log directory to the logarchive directory.

Note: If the log or logarchive directory is locked or inaccessible, then a log archive is not created.

About Siebel Server Manager

The Siebel Server Manager is the native management and administration interface for the Siebel Server and Siebel Enterprise Server. The Siebel Server Manager allows you to configure the parameters governing the operation of each component, and determine on which Siebel Servers a given component can operate.

Use the Siebel Server Manager to do the following:

- Start, stop, pause, and resume Siebel Servers, components, and tasks.
- Monitor the status and collect statistics across the Siebel Enterprise Server, Siebel Servers, components, and tasks.
- Manage the configuration of the Siebel Enterprise Server, Siebel Servers, components, and tasks.

You can operate the Server Manager by using one of two interfaces:

- The graphical user interface, or GUI, by using the server administration views in the Siebel application client.

Use the Server Manager GUI for most administrative duties because it includes greater user interface functionality (including the ability to search for and sort various fields within views) and a more intuitive view into the operation of Siebel Servers than does the command-line interface.

- The command-line interface, or the `svrMgr` program.

Use the command-line interface for batch-mode processing, because it can run from batch scripts by invoking script files with administration commands that must be run on a regular basis.

The Server Manager (both the GUI and the command-line interface) connects to the Siebel Gateway, which contains availability and connectivity information for the Siebel Servers within the Siebel Enterprise Server. The Server Manager then connects with each of the Siebel Servers and starts a Server Manager component task.

Note the following behavior:

- If you access the GUI, then Server Manager creates a task on every running Siebel Server.
- If you access the command-line interface without specifying a specific Siebel Server, then Server Manager creates a task on every running Siebel Server.

- If you start the command-line interface while specifying a specific Siebel Server, by using the /s or -s flag, then Server Manager creates a task on that specific Siebel Server alone, and all of the commands are targeted to that Siebel Server at the server level.

On each Siebel Server, the Server Manager task:

- Handles administration commands from the Server Manager
- Executes requested functions
- Returns each operation's results to the Server Manager

Note: Each session of Server Manager creates a separate Server Manager task. Therefore, you create a new Server Manager task each time that you access the server administration screens.

About Siebel Server Components

The various programs that operate on the Siebel Server are implemented as *components*. A component represents only a specific type of program. A component is executed or operated as a *task*, or instantiation of a component, on a specific Siebel Server. This topic includes the following information:

- ["About Server Component Modes"](#) on page 2-6
- ["About Server Component Types"](#) on page 2-7
- ["About Server Component Groups"](#) on page 2-7
- ["About Server Component Processes \(Shells\)"](#) on page 2-8

About Server Component Modes

Components execute tasks in one of three run modes, background, batch, or interactive:

- **Background-mode components.** Background-mode components execute tasks to perform background operations for the Siebel Server. After a background mode component task starts, it runs until you explicitly stop the task, or until the Siebel Server itself is shut down.

You can manually start a background mode component by using the Siebel Server Manager. Components with a Default Tasks parameter set to a value greater than zero might start automatically when the Siebel Server is started. Examples of background mode components include Transaction Router, Replication Agent, and Workflow Monitor Agent.

- **Batch mode-components.** You must manually start these components by using the component job process in the Server Manager GUI or by the Server Manager command-line interface. Batch-mode components end after the task has been performed. Examples of batch mode components include Database Extract and Enterprise Integration Manager.
- **Interactive-mode components.** Interactive-mode components start tasks automatically in response to client requests. Interactive mode component tasks execute for as long as the client maintains the session, and end when the client disconnects. Examples of interactive mode components include Synchronization Manager and Application Object Managers.

For a list of Siebel Server components and their associated run modes, see "[Siebel Server Components](#)" on page A-4.

About Server Component Types

Siebel Server supports multiple component types. Each type performs a specific function or job. A component type is configured with a set of parameters that determine its behavior to create an entity called a *defined component* (or *component*). Components are defined at the Siebel Enterprise Server level in *component groups*. Component groups are then assigned to one or more Siebel Servers within the Siebel Enterprise Server on which they can execute tasks.

When the Siebel Server is installed and initially configured, predefined components are automatically configured for each component type. These predefined components are then automatically assigned to each Siebel Server within the Siebel Enterprise Server. You can run your entire Siebel Business Applications deployment by using these predefined components, or you can modify their definitions and create new defined components to fine-tune your Siebel configuration. For a list of predefined Siebel Server components, see "[Siebel Server Components](#)" on page A-4.

The defined components feature allows you to create multiple defined components for a given component type, simplifying the process of starting various types of tasks that use different parameters, and managing components across multiple Siebel Servers.

For example, you might create one defined component for an Application Object Manager for the Siebel Sales application in Norwegian, and another for an Application Object Manager for the Siebel Service application, also in Norwegian. (Norwegian is an example of an *unshipped language*, as discussed in *Siebel Global Deployment Guide*.) Although these two defined components use the same component type, they service distinct sets of users with different functionality requirements, and are distinct entities that can be individually managed, configured, and administered. Defined components are configured in the Enterprise Component Definitions view of the Server Manager GUI.

Note: For the remainder of this guide, the term *component* refers to both predefined components and defined components that you might create or modify.

About Server Component Groups

Component groups are functional areas that involve logical groupings of Siebel Server components and multiple operating system processes. A component group consists of one or more components, which might be running in one or more operating system processes. Component groups act as:

- The unit of deployment on, or assignment to, a Siebel Server. In general, you include in a Siebel Server the group of components that are deployed on one or more servers.
- A unit for monitoring functionality of the interrelated components within the group (you can get a summary of the operational status at the component group status, which is determined by the individual states of the constituent components).
- A unit of control allowing you, in a single step, to make available or unavailable several interrelated components, such as those included in the Siebel Remote or Workflow Management component groups.

Siebel Business Applications provide several predefined component groups. For a list of the components contained within each component group, see ["Siebel Server Component Groups"](#) on page A-1. For information about creating your own component groups, see ["Creating a Custom Siebel Server Component Group"](#) on page 4-24.

About Server Component Processes (Shells)

The Siebel Server runs each component in its own separate process (or shell). These shells provide the interface for a component to communicate with shared memory, and use infrastructure facilities for logging, events, networking, and so on.

A shell performs the following actions when it is forked off:

- Initializes the logging and networking facility.
- Determines which component to run. The component is specified as a DLL (personality DLL), which is run by the Siebel Server either as part of the input parameters or as part of a network message.
- Attaches to shared memory.

The Siebel Server forks off an appropriate shell based on the component mode (interactive, batch, or background) and whether the component is object manager-based, multithreaded, or both. The tables in this topic identify the shell types created in various scenarios for interactive-mode, batch-mode, and background-mode components.

Note: To conserve system resources and minimize the number of processes running on the Siebel Server, disable the component groups that you do not plan to run. If you cannot disable a component group because you require components within the group, then you can set other components within the group that you do not require to Manual Start mode. For information about disabling component groups, see ["Unassigning Component Groups on a Siebel Server"](#) on page 4-8. For information about setting a component to start manually, see ["About Starting Siebel Server Components"](#) on page 4-19.

Shell Types for Interactive-Mode Components

[Table 2-2](#) identifies the shell types created for interactive-mode components.

Table 2-2 Shell Types for Interactive-Mode Components

Multithreaded	Object Manager-Based	Shell
False	False	siebsess
True	False	siebmtsh
True	True	siebmtshmw

Shell Types for Batch-Mode Components

[Table 2-3](#) identifies the shell types created for batch-mode components.

Table 2–3 Shell Types for Batch-Mode Components

Multithreaded	Object Manager-Based	Shell (Created at Bootstrap)	Shell (Created at Run Time)
False	False	siebproc	siebsh
False	True	siebprocmw	siebshmw
True	False	siebtsh	siebtsh
True	True	siebtshmw	siebtshmw

Shell Types for Background-Mode Components

[Table 2–4](#) identifies the shell types created for background-mode components.

Table 2–4 Shell Types for Background-Mode Components

Object Manager-Based	Shell (Created at Boot Time)	Shell (Created at Run Time)
False	siebproc	siebsh
True	siebprocmw	siebshmw

Examples of Shells for Siebel Server Components

The following are examples of shells for Siebel Server components:

- A background component that is not object manager-based is brought up in a siebproc shell. For example, Transaction Processor (alias TxnProc).
- An interactive component that is multithreaded and not object manager-based is brought up in a siebtsh shell. For example, Server Request Broker (alias SRBroker).
- A multithreaded, object manager-based component is brought up in a siebtshmw shell. For example, Call Center Object Manager for U.S. English (Call Center Object Manager (ENU), alias SCCObjMgr_enu).

Parameters Controlling the Number of Shells

The following parameters configure shell (process) startup for interactive, batch, and background mode components:

- Maximum MT Servers (alias MaxMTServers)
- Minimum MT Servers (alias MinMTServers)
- Maximum Tasks (alias MaxTasks)
- Default Tasks (alias DfltTasks)

For more information about configuring these parameters, see "[Siebel Enterprise, Server, and Component Parameters](#)" on page A-11 and "[Application Object Manager Parameters in Server Manager](#)" on page 9-3.

To review information about the shells forked off by the Siebel Server, access the Siebel Server log file. For information about viewing Siebel Server log files, see *Siebel System Monitoring and Diagnostics Guide*.

About the Siebel Application Interface

Siebel Application Interface is a module that enables communication between Siebel Web Clients and Siebel Servers. In Siebel Innovation Pack 2017, the Siebel Application

Interface replaces the Siebel Web Server Extension (SWSE). For information about installing and configuring Siebel Application Interface, see the *Siebel Installation Guide* for the operating system you are using.

About the Siebel File System and the File System Manager

The Siebel File System is a shared directory, or a set of directories on different devices, which is network-accessible to all of the Siebel Servers in the Siebel Enterprise Server. It contains the physical files used by the Siebel clients and Siebel Servers. To gain access to files, Web clients connect to the appropriate Siebel Server to request file uploads or downloads. The Siebel Server then accesses the Siebel File System by using the File System Manager (alias FSMSrvr) component. File System Manager processes these requests through interaction with the Siebel File System directories.

For information about administering the Siebel File System, see "[Administering the Siebel File System](#)" on page 8-5. For information about creating the Siebel File System, see the *Siebel Installation Guide* for the operating system you are using.

When using Siebel Developer Web Client for administrative tasks, you might want to connect directly to the Siebel File System without going through the File System Manager.

About the Siebel Management Pack

The Siebel Management Pack provides the underlying infrastructure components that are required to support the deployment features offered by the Oracle Enterprise Manager. The deployment of the Siebel Management Pack is optional. For more information, see *Implementation and Getting Started Guides for all Application Management Suite Products for Oracle Enterprise Manager 12C* on Oracle Technology Network. This document provides a brief introduction to the Siebel Management Pack, and describes the features that this product offers. For more information, visit this site:

<http://www.oracle.com/technetwork/oem/app-mgmt/index.html>

Configuring the System Architecture

This chapter provides an overview of configuring the Siebel Server and its components, modifying Siebel Server parameters, and reinstalling the Siebel Gateway and Siebel Servers, if necessary. This chapter includes the following topics:

- [About Configuring the Siebel Server and Its Components](#)
- [About System Environment Variables](#)
- [Configuring System Environment Variables](#)
- [Configuring Siebel Server Load Balancing](#)
- [Configuring the Session Manager](#)
- [Reinstalling the Siebel Gateway and Siebel Server](#)

About Configuring the Siebel Server and Its Components

Before starting the Siebel Server, you might want to modify how it has been configured. You must enable component groups on the Siebel Server. This topic describes some of the configuration-related tasks that you must perform to maintain or administer your Siebel CRM installation.

For more information about configuring Siebel Servers and server components by using the Server Manager GUI, see [Chapter 4, "Configuring Siebel Servers."](#) For more information about configuring Siebel Servers and server components by using the Server Manager command-line interface, see [Chapter 7, "Using the Siebel Server Manager Command-Line Interface."](#)

Note: The instructions in this chapter assume that you have successfully installed and initially configured the Siebel Gateway, the Siebel Enterprise, and at least one Siebel Server. For more information about performing configuration tasks by using the Siebel Management Console, see the *Siebel Installation Guide* for the operating system you are using.

Before starting the Siebel Server, you might want to add site-specific parameter values or overrides of existing values by using the Server Manager GUI.

You can configure a Siebel Server by modifying the parameters at the Siebel Server, component, or task level for the given Siebel Server. Changes to parameters at the Siebel Server level are inherited at the component and task levels. Changes to parameters at the component level are inherited at the task level. You can also modify parameters at the Siebel Enterprise Server level. Siebel Servers, components, or tasks

within the Siebel Enterprise Server inherit the values for modified parameters unless you have explicitly modified (overridden) these parameters at these levels (Siebel Server, component, or task level). For more information, see "[About Siebel System Parameters](#)" on page 4-2.

For information about configuration tasks using Siebel Management Console, see the *Siebel Installation Guide* for the operating system you are using.

About System Environment Variables

Environment variables are variables configured for a particular computer hosting an aspect of a Siebel deployment. These Siebel-specific environment variables configure interactions with the computer's operating system and various functions of Siebel Business Applications. Configure environment variables through the operating system of the individual computer. For information about configuring these variables, see "[Configuring System Environment Variables](#)" on page 3-4.

Environment variables configure a wide range of functionality and are covered in context-specific areas of the *Siebel Bookshelf*. The Siebel Bookshelf is available on Oracle Technology Network (OTN) and Oracle Software Delivery Cloud. It might also be installed locally on your intranet or on a network location.

[Table 3–1](#) provides a partial listing of environment variables for the Siebel Business Applications or that affect them, and it indicates one or more locations where each variable is documented. This list is not comprehensive. Some environment variables are set automatically. In general, you set environment variables explicitly only as you are instructed by documentation for Siebel Business Applications.

Table 3–1 Partial Listing of Siebel Environment Variables

Environment Variable	Where Documented
NLS_LANG	<i>Siebel Installation Guide</i> for the operating system you are using
NLS_SORT	<i>Siebel Installation Guide</i> for the operating system you are using
ORACLE_HOME	<i>Siebel Installation Guide</i> for the operating system you are using
PATH	<i>Siebel Installation Guide</i> for the operating system you are using
SIEBEL_CODEPAGE	<i>Siebel Installation Guide</i> for the operating system you are using
TEMP	<i>Siebel Installation Guide</i> for the operating system you are using
TMP	<i>Siebel Installation Guide</i> for the operating system you are using
LD_LIBRARY_PATH (Linux and Oracle Solaris)	<i>Siebel Installation Guide for UNIX</i>
JAVA_HOME	<i>Siebel Installation Guide for UNIX</i>
LANG	<i>Siebel Installation Guide for UNIX</i>
LC_ALL	<i>Siebel Installation Guide for UNIX</i>
LIBPATH (AIX)	<i>Siebel Installation Guide for UNIX</i>
NLS_DATE_FORMAT	<i>Siebel Installation Guide for UNIX</i>

Table 3–1 (Cont.) Partial Listing of Siebel Environment Variables

Environment Variable	Where Documented
ODBCINI	<i>Siebel Installation Guide for UNIX</i>
SHLIB_PATH (HP-UX)	<i>Siebel Installation Guide for UNIX</i>
SIEBEL_HOME	<i>Siebel Installation Guide for UNIX</i>
SIEBEL_GATEWAY_ROOT	<i>Siebel Installation Guide for UNIX</i>
SIEBEL_SERVER_ROOT	<i>Siebel Installation Guide for UNIX</i>
SIEBEL_ROOT	<i>Siebel Installation Guide for UNIX</i>
SIEBEL_ENTERPRISE	<i>Siebel Installation Guide for UNIX</i>
SIEBEL_UNIXUNICODE_DB	<i>Siebel Installation Guide for UNIX</i>
TNS_ADMIN	<i>Siebel Installation Guide for UNIX</i>
SIEBEL_ASSERT_MODE	<i>Siebel Performance Tuning Guide</i> <i>Siebel System Monitoring and Diagnostics Guide</i>
SIEBEL_OSD_LATCH	<i>Siebel Performance Tuning Guide</i>
SIEBEL_OSD_MAXLIMITS	<i>Siebel Performance Tuning Guide</i>
SIEBEL_OSD_NLATCH	<i>Siebel Performance Tuning Guide</i>
SIEBEL_OSD_PTHREAD_STACK_SIZE	<i>Siebel Performance Tuning Guide</i> 2007183.1 (Article ID) on My Oracle Support Note: This environment variable applies only to supported versions of UNIX or Linux operating systems.
SIEBEL_SARMBufferSize	<i>Siebel Performance Tuning Guide</i>
SIEBEL_SARMFileSize	<i>Siebel Performance Tuning Guide</i>
SIEBEL_SARMLevel	<i>Siebel Performance Tuning Guide</i>
SIEBEL_SARMMaxFiles	<i>Siebel Performance Tuning Guide</i>
SIEBEL_SARMPeiod	<i>Siebel Performance Tuning Guide</i>
SIEBEL_CRASH_HANDLER	<i>Siebel System Monitoring and Diagnostics Guide</i>
SIEBEL_DIAG_STORE	<i>Siebel System Monitoring and Diagnostics Guide</i>
SIEBEL_LOG_ARCHIVES	<i>Siebel System Monitoring and Diagnostics Guide</i>
SIEBEL_LOG_DIR	<i>Siebel System Monitoring and Diagnostics Guide</i>
SIEBEL_LOG_EVENTS	<i>Siebel System Monitoring and Diagnostics Guide</i>
SIEBEL_SESSMGR_TRACE	<i>Siebel System Monitoring and Diagnostics Guide</i>
SIEBEL_SISNAPI_TRACE	<i>Siebel System Monitoring and Diagnostics Guide</i>
SIEBEL_STDERRROUT	<i>Siebel System Monitoring and Diagnostics Guide</i>
SIEBEL_DATA_SOURCE	<i>Using Siebel Tools</i>
SIEBEL_TABLE_OWNER	<i>Using Siebel Tools</i>
SIEBEL_FILE_ENCODING	<i>Siebel Marketing User Guide</i>
SPELLCHECKLEVEL1	Set to True when using the spell check feature with outbound email messages. For more information about this feature, see <i>Siebel Email Administration Guide</i> .

Table 3–1 (Cont.) Partial Listing of Siebel Environment Variables

Environment Variable	Where Documented
RESOLV_MULTI	1435205.1 (Article ID) on My Oracle Support Note: This environment variable applies only to supported versions of Oracle Enterprise Linux.

Configuring System Environment Variables

This topic describes how to configure system environment variables on Windows and on UNIX. For more information about Siebel-specific environment variables, see ["About System Environment Variables"](#) on page 3-2. For a list of some of the Siebel environment variables, see [Table 3–1](#).

Configuring an Environment Variable on Windows

This procedure describes how to configure an environment variable on Windows.

To configure an environment variable on Windows

1. Choose Start, Settings, Control Panel, and then double-click System.
2. Click the Advanced tab, then click Environment Variables.
3. In the System Variables section, click New to create a new environment variable.
For a partial list of Siebel environment variables, see [Table 3–1](#).
4. Set the Variable Name field to the name of a Siebel environment variable.
5. Set the Variable Value field to the value for the Siebel environment variable.
6. Restart the computer for the environment variables to take effect.

Configuring an Environment Variable on UNIX

This procedure describes how to configure an environment variable on UNIX.

To configure an environment variable on UNIX

1. Log in as the Siebel Service owner user.
2. Run the `siebenv.sh` or `siebenv.csh` script to set Siebel environment variables. For more information about these scripts, see *Siebel Installation Guide for UNIX*.
3. Depending on the type of UNIX operating system that you use, enter a command like the following to set the environment variable.

For Korn shell:

```
export Siebel_Environment_Variable=Variable_Value
```

For C shell:

```
setenv Siebel_Environment_Variable Variable_Value
```

where:

- `Siebel_Environment_Variable` is a Siebel-specific environment variable.
- `Variable_Value` is the setting for the environment variable.

For example, enter the following command for C shell:

```
setenv SIEBEL_SARMLlevel 1
```

4. Restart the computer for the environment variables to take effect.

Configuring Siebel Server Load Balancing

Siebel Server load balancing distributes the workload across multiple Siebel Servers. For background information and information about initially configuring your Siebel CRM server environment, see *Siebel Deployment Planning Guide* and the *Siebel Installation Guide* for the operating system you are using.

This topic includes the following information:

- ["Rebalancing Siebel Server Loads"](#) on page 3-5
- ["Troubleshooting Siebel Native Load Balancing"](#) on page 3-5
- ["Verifying Load Balancing Port Access on Siebel Servers"](#) on page 3-6

Rebalancing Siebel Server Loads

Server loads can become unevenly distributed for several reasons:

- You have just added a new Siebel Server to the network. It will have a low workload compared to other Siebel Servers.
- You have just enabled an Application Object Manager on a Siebel Server. It will have a lower workload than other Application Object Managers on different Siebel Servers.
- There was a server configuration or request routing problem that prevented even distribution of workloads. When this problem is corrected, one or more Siebel Servers will have low workloads.

Siebel native load balancing distributes workloads based on logins. Users must terminate existing sessions and log in to the new sessions to cause workloads to be redistributed. For example, you have 1000 concurrent user sessions running on three Siebel Servers. You then add a fourth Siebel Server. Until all of the users end their sessions and log in again, the load is not evenly distributed between all four servers.

Whenever possible, let normal user login behavior rebalance Siebel Server workloads. Intervene only when absolutely necessary. To rebalance server workloads, stop SCBroker on a Siebel Server. Doing so directs workload away from that server, but does not affect existing user sessions. However, session reconnect does not work for this server. If the connection times out, and user requests come through a Siebel Application Interface other than the one used for login, then the session is lost.

Troubleshooting Siebel Native Load Balancing

This topic provides guidelines for resolving problems with Siebel native load balancing. To resolve a problem, look for it in the list of symptoms or error messages in [Table 3-2](#). Some problem solutions in the table require changing the function of server components.

Table 3–2 Resolving Siebel Native Load Balancing Problems

Problem	Cause	Solution
Users do not get a login page. The browser might display Server Busy Error.	Verify TCP port access for Siebel Servers, Siebel Gateway, and Siebel Application Interface.	See " Verifying Load Balancing Port Access on Siebel Servers " on page 3-6.
	Increase the Siebel Application Interface logging level.	To turn on detailed Siebel Application Interface logging, increase the log level for Siebel Application Interface. For more information, see the information about configuring the Siebel Application Interface in the <i>Siebel Installation Guide</i> for the operating system you are using. The logs for this module are located in <code>SIEBEL_AI_ROOT/applicationcontainer/logs</code> .
Users can connect but loads are not balanced evenly between Siebel Servers	Unequal loads might be caused by characteristics of users and jobs.	Because jobs are distributed in a round-robin fashion, it is normal for a snapshot of the servers to show somewhat unequal loads. Unequal loads can be caused by several things, including the nature of the jobs and the rate at which users log in and log out on different servers. Over a longer period, the number of sessions handled by each server evens out.
	Siebel Servers do not have equal access to computing resources.	Verify that all of the Siebel Servers have equal access to computing resources such as CPU and memory.
	A Siebel Server has recently added or has been restarted.	Load balancing is based on user logins. During the process in which current sessions are terminated and new sessions are started, the new Siebel Server is included in the load sharing.
	A Siebel Application Interface cannot route requests to one or more Siebel Servers.	Check for connectivity problems between the Siebel Application Interface and the Siebel Server with the low workload, as described earlier in this table.
	A Siebel Server is rejecting an unusual number of user requests.	Check the Siebel Application Interface log files for <code>SISNAPI Connection Refused</code> messages. Possible causes are: <ul style="list-style-type: none"> ■ The SCBroker component either is not running or is listening on a different port. ■ The requested Application Object Manager is not running or cannot run any more tasks. ■ The requested Application Object Manager has a task or thread that is not responding. ■ The Application Object Manager cannot communicate with the database server.
	A Siebel Server has functional or configuration problems.	Enable server diagnostics. Look for problems with components. Verify that the basic configuration is correct. For more information about monitoring and diagnosing server problems, see <i>Siebel System Monitoring and Diagnostics Guide</i> .

Verifying Load Balancing Port Access on Siebel Servers

This topic describes how to verify access to the load balancing port (that is, the port on which the SCBroker component listens) on your Siebel Servers.

To verify load balancing port access on your Siebel Servers

1. On the computer where Siebel Application Interface is running, telnet to the SCBroker port (such as 2321) on each Siebel Server.

For example, if a Siebel Server has the host name `SiebSrvr1`, then use the following command:

```
telnet SiebSrvr1 2321
```

If the connection succeeds, then there is load balancing port access. The connection times out after 500 ms.

If the connection fails, with the message `Could not open connection to server`, then complete the remaining steps that follow.

2. Verify that the Siebel Business Applications that you want are running on each Siebel Server.
3. On each Siebel Server, verify that SCBroker is running and is configured to listen on port 2321.
4. Verify that the operating system is not blocking access to the SCBroker port.
5. Check that no other networking device, such as a firewall, is blocking access to the SCBroker port.

Related Topics

["About Siebel Connection Broker \(SCBroker\)"](#) on page 8-3

Configuring the Session Manager

The Session Manager is a layer within the Siebel Application Interface and Application Object Manager that manages TCP/IP (SISNAPI) connections between clients and Application Object Managers. The Session Manager primarily manages Siebel Application Interface to Siebel Server communications. It is not a stand-alone component, but it is embedded in Siebel Application Interface and in an Object Manager component that is directly accessed through an external interface, such as Component Object Model (COM).

Note: SISNAPI is a proprietary messaging format used for communication into Siebel Servers, and between multiple Siebel Servers. The acronym stands for Siebel Internet Session API (Application Program Interface).

The Session Manager is primarily responsible for establishing and managing connections from the client to the Application Object Manager. A connection is established for each new session request, and is kept open or terminated based on connection multiplexing settings. The Session Manager allows multiple client sessions to share the same pool of connections, thereby minimizing resource usage and maximizing overall performance.

When a client requests a new session, the Siebel Application Interface receives the HTTP request, translates the request into SISNAPI messaging format, and invokes the Session Manager, which is embedded in the Siebel Application Interface, to obtain a physical connection to the Siebel Server. The Session Manager creates a new, temporary connection, which is load-balanced to an available Siebel Server.

After this temporary connection is made to a Siebel Server, Session Manager checks to see whether there are enough connections to the target process. If there are enough TCP connections, then the temporary connection is dropped and the existing connection is used for this new user session. If a connection is not available, then the temporary connection is retained. For more information about this process, see *Siebel Performance Tuning Guide*, which describes the use of the parameter Number of Sessions for each SISNAPI Connection (alias `SessPerSisnConn`).

After Session Manager opens a connection to the Siebel Server, it closes connections based on the time the connection remains idle. The parameter SISNAPI Connection Maximum Idle Time (alias ConnIdleTime) controls this feature. After reaching the configured idle period, the connection is disconnected by the Application Object Manager process.

A benefit of the ConnIdleTime parameter is to manage connections that pass through a firewall placed between the Siebel Application Interface and the Siebel Server. Because firewalls block idle connections, the ConnIdleTime parameter can be configured to disconnect idle connections before they are blocked by the firewall. This setting avoids future connection problems between the Siebel Application Interface and the Siebel Server.

Note: Only enable the ConnIdleTime parameter at the component level, specifically, for Application Object Manager components.

For more information about communication between the client and the Siebel application, see *Siebel Performance Tuning Guide*.

Parameters that modify Session Manager and SISNAPI connections are available for each component at the component level. For more information about these and other parameters, see "[Siebel Enterprise, Server, and Component Parameters](#)" on page A-11.

Reinstalling the Siebel Gateway and Siebel Server

In some cases, you might have to reinstall the Siebel Gateway and Siebel Servers. These cases include scenarios when you want to:

- Rename the computer on which the Siebel Gateway, Siebel Servers, or both are running.
- Make structural changes to the directory where the Siebel Gateway, Siebel Servers, or both are installed.
- Move the Siebel Gateway, Siebel Servers, or both to another computer.

Each of the listed operations requires you to uninstall and reinstall both the Siebel Gateway and Siebel Servers. Uninstalling also requires that you first perform the necessary tasks to remove associated configuration data. For more information about installing and uninstalling Siebel Servers and the Siebel Gateway and about tasks for configuring and for removing configuration data, see the *Siebel Installation Guide* for the operating system you are using.

Caution: In general, uninstalling and reinstalling server modules can present severe consequences for your application environment. Avoid these tasks and associated tasks wherever possible or perform them only when necessary.

You uninstall and reinstall Siebel Servers and the Siebel Gateway in the following sequence.

To uninstall and reinstall server entities

1. Uninstall each Siebel Server.
2. Uninstall the Siebel Gateway.

3. Reinstall the Siebel Gateway.
4. Reinstall each Siebel Server.

After installation and initial configuration, you perform any additional necessary Siebel Server configuration tasks, such as to define new components, enable or disable components and component groups, assign component groups to Siebel Server, and so on. You must also reextract all of the Mobile Web Clients. For information about extracting Mobile Web Clients databases, see *Siebel Remote and Replication Manager Administration Guide*.

Configuring Siebel Servers

This chapter describes Siebel Server configuration tasks and processes that you perform by using the Siebel Server Manager GUI and gives background information about Siebel system parameters. It includes the following topics:

- [About the Server Manager GUI](#)
- [About Siebel System Parameters](#)
- [Configuring the Siebel Enterprise Server](#)
- [Configuring the Siebel Server](#)
- [Checking Your Siebel Enterprise and Siebel Server Configurations](#)
- [About Siebel Server Component Definitions](#)
- [Process of Creating a Custom Siebel Server Component](#)
- [Deleting a Siebel Server Component Definition](#)
- [Deactivating a Siebel Server Component Definition](#)
- [Advanced Configuration Tasks](#)

About the Server Manager GUI

The Siebel Server Manager graphical user interface (GUI) consists of the views in the following server administration screens, which are available from the application Site Map:

- Administration - Server Configuration
- Administration - Server Management
- Server Jobs

Note: The Siebel Server Manager GUI screens allow you to use only the query operator LIKE.

In general, use the Siebel Server Manager GUI to perform most administrative tasks, because it provides a more intuitive view into the operation of Siebel Servers than does the command-line interface.

Note: By default, the Siebel Server Manager GUI is available on every Siebel client, and is accessible to users with Siebel administrator responsibility. This feature allows Siebel administrators to perform administration tasks from any client on the network. Therefore, it is important to grant the Siebel administrator responsibility only to designated Siebel administrators.

About the Enterprise Explorer View

The Administration - Server Configuration screen contains a view for reviewing enterprise data in an Explorer or hierarchical format. The Enterprise Explorer view provides an alternate means of navigation and a comprehensive layout of the enterprise data. You access this view by selecting Enterprise Explorer from the link bar.

About the Process Failure Diagnostics View

The Administration - Server Management screen contains the Process Failure Diagnostics view, which you can use for investigating process failures for Siebel Server components. You access this view by selecting Diagnostics from the link bar.

Related Topics

[Chapter 7, "Using the Siebel Server Manager Command-Line Interface"](#)

Related Books

Siebel Installation Guide for the operating system you are using

Siebel Applications Administration Guide

Siebel Security Guide

Siebel System Monitoring and Diagnostics Guide

About Siebel System Parameters

The Siebel application uses parameter values based on the level at which they are set. Parameter values at the highest levels are inherited by the same parameter at lower levels. For example, a parameter set at the enterprise level contains the same value for the same parameter at the server and component level, unless the value is overridden at a lower level. If a change is made to that parameter at the enterprise level, then this value is inherited down to the lower levels. [Table 4-1](#) lists the parameter-setting levels in order from highest to lowest.

If a parameter value is set at a lower level, and a new change is made to the same parameter at a higher level, then the new change does not inherit down to the lower level unless the override is deleted at that lower level.

Note: Do not set lower-level parameters to a blank or empty value. To negate a parameter value, use the appropriate `delete parameter override` command.

Once you set a parameter at a lower level, this value creates an entry in the Siebel Gateway registry and, from that time on, you must maintain it at this level. That is, any further changes that are to affect this level must be made at this level unless you delete the override.

Note: Querying for a specific parameter in either the Parameter field or the Alias field returns matches from both fields. For example, querying in the Parameter field by using the expression File* returns the result Siebel File System, because the parameter's alias is FileSystem.

Table 4-1 lists the parameter-setting levels in order, from highest to lowest. Named subsystem parameters can apply to entities at different levels.

Table 4-1 Hierarchy of System Parameters

Level	System Parameter	Comment
1	Default from library	Default, hard-coded values from the library. Does not apply for passwords and other parameters that require user-supplied values.
2	Siebel Enterprise parameter	For more information, see "About Siebel Enterprise Server Parameters" on page 4-4 and "Configuring Siebel Enterprise Parameters" on page 4-13.
3	Siebel Server parameter	For more information, see "About Siebel Server Parameters" on page 4-5 and "Configuring Siebel Server Parameters" on page 4-21.
4	Siebel Server component parameter, enterprise level	Enterprise-level Siebel Server component parameters are set by configuring component definition parameters. For more information, see "Configuring Siebel Enterprise Component Definition Parameters" on page 4-13 and "About Siebel Server Component Definitions" on page 4-22.
5	Siebel Server component parameter, server level	For more information, see "About Siebel Component Parameters" on page 4-5 and "Configuring Siebel Server Component Parameters" on page 4-21.
6	Siebel Server component task parameter	Configure these parameters mainly for batch tasks or when invoking tasks from a script or a workflow process. For more information, see "About Task Parameters" on page 4-6, "Starting a Component Job" on page 6-6, and "Configuring Siebel Server Task Dynamic Parameters" on page 6-13.

This topic contains the following information:

- ["About Advanced and Hidden Parameters"](#) on page 4-4
- ["About Parameter Availability Status"](#) on page 4-4
- ["About Siebel Enterprise Server Parameters"](#) on page 4-4
- ["About Siebel Server Parameters"](#) on page 4-5
- ["About Siebel Component Parameters"](#) on page 4-5
- ["About Task Parameters"](#) on page 4-6
- ["About Named Subsystem Parameters"](#) on page 4-6

Related Topics

["Deleting System Parameter Overrides"](#) on page 4-31

["Parameter Management Commands"](#) on page 7-20

About Advanced and Hidden Parameters

Parameters that affect or modify advanced product functionality are, by default, hidden from the Server Manager GUI.

To make advanced or hidden parameters visible, click Advanced or Hidden on the parameter views for the enterprise, Siebel Server, or components. To restore the default view, click Reset.

Related Topics

["Configuring Siebel Server Component Parameters"](#) on page 4-21

["List Commands"](#) on page 7-8

About Parameter Availability Status

The Server Manager GUI provides parameter availability status for system parameters at the following levels: enterprise, Siebel Server, component definition, component, task, and session. Certain parameters become available or effective only after specific Siebel Server operations are performed. Review the parameter availability status options in [Table 4-2](#) to determine the type of action necessary to make your parameter change effective.

Table 4-2 *Parameter Availability Status Options*

Availability Status	Description
Immediately	These parameters are effective immediately and require no further Siebel Server operations. These parameter are also known as <i>dynamic</i> parameters. All other parameters are <i>static</i> parameters.
At Next Task	These parameters are effective at the start of the next task.
At Component Restart	These parameters require a restart of the server component before they become effective.
At Server Restart	These parameters require a restart of the Siebel Server before they become effective.
Require Reconfiguration	These parameters require the component definition to be reconfigured before they become effective.

Related Topics

["Reconfiguring Siebel Server Component Definitions"](#) on page 4-27

["Administering Siebel Servers"](#) on page 6-1

["Administering Siebel Server Components"](#) on page 6-3

["Administering Component Jobs"](#) on page 6-5

About Siebel Enterprise Server Parameters

Enterprise parameters set the attributes of the entire Siebel Enterprise Server. These parameters are initially set when the Siebel Enterprise Server is initially configured by using the Siebel Management Console. Each Siebel Server installed and configured in the Siebel Enterprise Server inherits these enterprise parameters. Many of the parameters that can be set at the enterprise level are server or named subsystem parameters, which can then be modified or overridden on each Siebel Server.

For example, if a Siebel environment contains multiple Siebel Servers, and the component parameters Maximum MT Servers (alias MaxMTServers) and Maximum Tasks (alias MaxTasks) are set at the enterprise level for a specific component with the values 5 and 100, respectively, then, unless override values are in effect, *each* Siebel Server in the environment runs this specific component with a maximum of 5 server processes (MaxMTServers) and a maximum 100 tasks (MaxTasks). The values 100 and 5 do not apply to the enterprise as a whole, but provide values for each instance of the component on an individual Siebel Server.

Note: Setting parameters at the enterprise level sets generic parameters used by all of the Siebel Servers and components across the enterprise. To set component-specific parameters for all components across an enterprise, configure the component definition parameters.

Related Topics

["About Siebel System Parameters"](#) on page 4-2

About Siebel Server Parameters

Siebel Server parameters set the attributes of each Siebel Server. These parameters are either used by the Siebel Server for its own operation, such as Shutdown Wait Time, or inherited by the components assigned to that Siebel Server.

The entire set of parameters for a given Siebel Server is a combination of the enterprise parameters inherited from the enterprise, and those specified when the Siebel Server is initially configured. Either type can be modified for any given Siebel Server.

If Siebel Server-level parameters are changed, then any future configurations to Siebel Enterprise Server-level parameters do not cascade down to the Siebel Server parameter level for that particular parameter. To restore this functionality, see the description of the appropriate `delete parameter override` command.

New values for Siebel Server-level dynamic parameters, which are parameters marked as Effective Immediately, apply to subsequently started tasks, unless these values are overridden at a lower level.

New values for static parameters, which are parameters not marked Effective Immediately, do not apply to subsequently started tasks until you stop and restart the Siebel Server system service. For both fixed and static parameters, the Server Manager views continue to show both the current value and the value upon Siebel Server restart.

Related Topics

["About Siebel System Parameters"](#) on page 4-2

["Parameter Management Commands"](#) on page 7-20

About Siebel Component Parameters

Siebel component parameters set the attributes specific to a particular component type. These parameters are set initially when the defined component is created. For each component assigned to a Siebel Server, the component inherits the Siebel Enterprise and Siebel Server parameters applicable to that Siebel Server. The three types of parameters (except those marked Fixed when the defined component was created) can be overridden for the particular component on that Siebel Server.

If component-level parameters are changed, then any future configurations to Siebel Enterprise Server or Siebel Server-level parameters do not cascade down to the component parameter level for that particular parameter. To restore this functionality, see the description of the appropriate `delete parameter override` command.

New values for component-level dynamic parameters, which are parameters marked as Effective Immediately, apply to subsequently started tasks, unless these values are overridden at a lower level.

New values for static parameters (that is, parameters that are not marked Effective Immediately) do not apply to subsequently started tasks until you stop and restart the Siebel Server system service. For both fixed and static parameters, the Siebel Server Manager views continue to show both the current value and the value upon Siebel Server restart.

Related Topics

["About Siebel System Parameters"](#) on page 4-2

["Parameter Management Commands"](#) on page 7-20

About Task Parameters

Task parameters control the execution of a specific task. These parameters consist of Siebel Enterprise, Siebel Server, and component-level parameters for the Siebel Server and the component for which the task is being executed, as well as task-specific parameters specified when you start a task. Task parameters are set or overridden when you first start the task. After a task is running, only dynamic parameters can be changed.

Note: The delay before the new parameter value is picked up and used by a running task varies by component, depending on how often the tasks for a particular component recheck their parameter values.

Related Topics

["About Siebel System Parameters"](#) on page 4-2

About Named Subsystem Parameters

Named subsystems are groupings of defined enterprise parameters, which allow the Siebel Server to manage multiple sets of parameter values. Like other server constructs, such as component definitions, server parameters, enterprise parameters, and component parameters, they are stored in the Siebel Gateway. When a Siebel Server starts, it retrieves this information and creates a copy of the named subsystems in shared memory. You can create named subsystems by using the Server Manager GUI or command-line interface.

The Server Manager GUI also refers to named subsystems as enterprise profiles. You create new named subsystems in the Profile Configuration subview of the Enterprises view in the Administration - Server Configuration screen.

By using named subsystems, the Application Object Manager can maintain several different values for a particular parameter. The value used by the Application Object Manager depends on the context. In other words, an Application Object Manager has several groups of parameters with context-dependent values: in context 1, parameters PA and PB have values V1A and V1B, respectively, whereas in context 2, the same parameters have values V2A and V2B.

For example, the Application Object Manager uses different configuration information that depends on the data source on which the business components are based. Which data source, and data source configuration, is used for a particular business component is context information that can come from several different sources. A business component can specify a data source in the compiled repository file, or a client can select a data source from several available data sources. Configuration information like database case sensitivity can have different values depending on the data source.

The parameters that have a context dependency are defined as named subsystem parameters. The component code that uses these named subsystems can request the subsystem parameter values by using a context name and will receive the value belonging to the named subsystem.

Named subsystem parameters are set at the enterprise level only. Parameter names associated with a data source usually start with DS so they do not conflict with the other parameters from the levels 2 to 6 in [Table 4-1](#). Named subsystem parameters have a higher priority than the default parameter settings that are hard-coded in their library.

Where they apply, named subsystem parameters override parameters set at the Siebel Enterprise, Siebel Server, and server component levels.

Related Topics

["About Siebel System Parameters"](#) on page 4-2

["Creating Siebel Enterprise Server Named Subsystems"](#) on page 4-12

["Configuring Siebel Enterprise Server Named Subsystem Parameters"](#) on page 4-11

["Named Subsystem Management Commands"](#) on page 7-21

Configuring the Siebel Enterprise Server

This topic lists the configuration tasks applicable to the Siebel Enterprise Server. For more information about the Siebel Enterprise Server and the overall system architecture, see [Chapter 2, "Siebel Enterprise Server Architecture."](#) You initially configure the Siebel Enterprise Server modules using Siebel Management Console, as described in the *Siebel Installation Guide* for the operating system you are using.

This topic contains the following information:

- ["About Assigned and Unassigned Component Groups"](#) on page 4-8
- ["Unassigning Component Groups on a Siebel Server"](#) on page 4-8
- ["Assigning Component Groups on a Siebel Server"](#) on page 4-9
- ["About Enabled and Disabled Component Groups"](#) on page 4-10
- ["Enabling Component Groups on a Siebel Enterprise Server"](#) on page 4-11
- ["Disabling Component Groups on a Siebel Enterprise Server"](#) on page 4-11
- ["Configuring Siebel Enterprise Server Named Subsystem Parameters"](#) on page 4-11
- ["Creating Siebel Enterprise Server Named Subsystems"](#) on page 4-12
- ["Configuring Siebel Enterprise Parameters"](#) on page 4-13
- ["Configuring Siebel Enterprise Component Definition Parameters"](#) on page 4-13
- ["About System Alert Notification"](#) on page 4-14

- ["Configuring System Alert Notification"](#) on page 4-14
- ["Troubleshooting System Alert Notification"](#) on page 4-16
- ["Configuring Component Job Templates"](#) on page 4-16
- ["Synchronizing Components on a Siebel Enterprise Server"](#) on page 4-17

About Assigned and Unassigned Component Groups

Component groups are assigned to Siebel Servers within a Siebel Enterprise Server. Both predefined and defined components groups are automatically assigned to each Siebel Server installed and configured within an existing Siebel Enterprise Server. Component groups must be assigned to Siebel Servers before tasks can be started for the components belonging to the component group. Only make changes to the component group assignment if you want to unassign or reassign component groups to different Siebel Servers.

Unassigning a component group on a Siebel Enterprise Server results in:

- No allocation of space in the shared memory segment for component groups after startup.
- The removal of the component group entries from the Siebel Gateway data.
- A loss of any component group customization (for example, parameter overrides at the component level).

Changes to the component group assignment state take effect only when the Siebel Server system service and Siebel Gateway system service are restarted.

Generally, only unassign a component group if the component group is not planned for future deployment on a particular server. Alternatively, you can disable a component group temporarily.

Note: Unassign or disable component groups that are not intended to operate on that Siebel Server to reduce unnecessary consumption of server resources. Also, do not initially enable any component groups that are not specifically intended for a given Siebel Server.

Related Topics

["Unassigning Component Groups on a Siebel Server"](#) on page 4-8

["Assigning Component Groups on a Siebel Server"](#) on page 4-9

["About Enabled and Disabled Component Groups"](#) on page 4-10

["Disabling Component Groups on a Siebel Enterprise Server"](#) on page 4-11

Unassigning Component Groups on a Siebel Server

This topic describes how to unassign component groups on a Siebel Server.

Note: Unassigning a component group from a Siebel Server results in a loss of component group customization, for example, parameter settings.

To unassign a component group on a Siebel Server

1. Shut down the Siebel Server that contains the component group that you want to unassign.
2. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
3. In the Component Groups list, select the component group of interest.
4. In the Component Group Assignments list, select the Siebel Server of interest.
5. Click Unassign.
The Assigned? field for the specified component group on the specified Siebel Server no longer contains a check mark.
6. Restart the Siebel Server that previously contained the unassigned component group.
7. For the change to take effect, stop and restart the Siebel Server system service and Siebel Gateway system service.

Related Topics

["Configuring the Siebel Enterprise Server" on page 4-7](#)

["About Assigned and Unassigned Component Groups" on page 4-8](#)

["Administering the Siebel Gateway System Service" on page 5-3](#)

["Administering the Siebel Server System Service" on page 5-7](#)

["Starting a Siebel Server" on page 6-1](#)

["Shutting Down a Siebel Server" on page 6-2](#)

Assigning Component Groups on a Siebel Server

This topic describes how to assign component groups on a Siebel Server. You can assign component groups that are currently unassigned.

To assign a component group on a Siebel Server

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. In the Component Groups list, select the component group of interest.
3. In the Component Group Assignments list, select the Siebel Server of interest.
4. Click Assign.
The Assigned? field for the specified component group on the specified Siebel Server now contains a check mark.
5. For the change to take effect, stop and restart the Siebel Server system service and the Siebel Gateway system service.

Related Topics

["Configuring the Siebel Enterprise Server" on page 4-7](#)

["About Assigned and Unassigned Component Groups" on page 4-8](#)

["Administering the Siebel Gateway System Service" on page 5-3](#)

["Administering the Siebel Server System Service" on page 5-7](#)

About Enabled and Disabled Component Groups

An enabled component group, at the enterprise level and server level, is one of the necessary conditions for execution of server component tasks belonging to that component group. Component groups are enabled and disabled independently at the enterprise and server level.

To enable or disable a component group at the enterprise level, the component group must be assigned on one or more Siebel Servers. To enable or disable a component group at the Siebel Server level, the component group must be assigned on this Siebel Server.

When creating a new component group, first assign the component group to the appropriate Siebel Servers before enabling the component group at the enterprise and server levels.

- **Enabled.** The component group is enabled at the enterprise level. You can then configure the component group run state so tasks can be started for components within the component group.
- **Disabled.** The component group is disabled at the enterprise level. You cannot configure the component group run state, and tasks cannot be started for components within the component group.

Disabling a component group results in:

- Components that are unavailable on Siebel Servers, therefore, tasks cannot be started (existing tasks run to completion)
- No allocation of space in the shared memory segment for those components when the Siebel Server is restarted

Note: Unassigning or disabling component groups that you do not need will reduce the unnecessary consumption of server resources. If a component group is not planned for immediate deployment on a particular Siebel Server but might be deployed in the future, then you can disable the component group on that Siebel Server. (For a Siebel Server that has not yet been configured, do not enable the component group in the Siebel Management Console.) If a component group is not planned for deployment, then you can remove it from a Siebel Server by unassigning the component group.

For procedures for enabling and disabling component groups, see the following:

- ["Enabling Component Groups on a Siebel Enterprise Server"](#) on page 4-11
- ["Disabling Component Groups on a Siebel Enterprise Server"](#) on page 4-11
- ["About Assigned and Unassigned Component Groups"](#) on page 4-8
- ["Enabling Component Groups on a Siebel Server"](#) on page 4-18
- ["Disabling Component Groups on a Siebel Server"](#) on page 4-19

Related Topics

["About Assigned and Unassigned Component Groups"](#) on page 4-8

["Checking Your Siebel Enterprise and Siebel Server Configurations"](#) on page 4-22

Enabling Component Groups on a Siebel Enterprise Server

This topic describes how to enable component groups on a Siebel Enterprise Server.

To enable a component group on a Siebel Enterprise Server

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. In the Component Groups list, select the disabled component group of interest.
3. Click Enable.

The Enable State field of the component group record changes to Enabled.

4. If the component group contains batch-mode components, then synchronize Siebel Server components.
5. For the change to take effect, stop and restart the Siebel Server system service.

Related Topics

["Configuring the Siebel Enterprise Server" on page 4-7](#)

["About Enabled and Disabled Component Groups" on page 4-10](#)

["Synchronizing Components on a Siebel Enterprise Server" on page 4-17](#)

["Enabling Component Groups on a Siebel Server" on page 4-18](#)

[Chapter 5, "Administering Server System Services"](#)

Disabling Component Groups on a Siebel Enterprise Server

This topic describes how to disable component groups on a Siebel Enterprise Server.

To disable a component group on a Siebel Enterprise Server

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. In the Component Groups list, select the enabled component group of interest.
3. Click Disable.

The Enable State field of the component group record changes to Disabled.

4. If the component group contains batch-mode components, then synchronize Siebel Server components.
5. For the change to take effect, stop and restart the Siebel Server system service.

Related Topics

["Configuring the Siebel Enterprise Server" on page 4-7](#)

["About Enabled and Disabled Component Groups" on page 4-10](#)

["Synchronizing Components on a Siebel Enterprise Server" on page 4-17](#)

["Disabling Component Groups on a Siebel Server" on page 4-19](#)

[Chapter 5, "Administering Server System Services"](#)

Configuring Siebel Enterprise Server Named Subsystem Parameters

This topic describes how to configure Siebel Enterprise Server named subsystem parameters.

To configure named subsystem parameters on a Siebel Enterprise Server

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. Select the Profile Configuration view tab.
3. In the Profile Configuration list, select the named subsystem (profile) of interest.
4. In the Profile Parameters list, select the parameter of interest and configure its value.

Related Topics

["About Named Subsystem Parameters" on page 4-6](#)

["Configuring the Siebel Enterprise Server" on page 4-7](#)

["Creating Siebel Enterprise Server Named Subsystems" on page 4-12](#)

Creating Siebel Enterprise Server Named Subsystems

This topic describes how to create Siebel Enterprise Server named subsystems.

The named subsystem parameters override the parameters that are set at the Enterprise Server, Siebel Server, and server component levels.

You can create and configure the named subsystems by using either the Siebel Server Manager GUI or the command-line interface.

To create named subsystems

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. Select the Profile Configuration view tab.
3. In the Profile Configuration list, click New.
 - a. In the Profile field, type the name of the named subsystem (profile). Do not exceed 30 characters when defining the name of the named subsystem.
 - b. In the Alias field, type the alias of the named subsystem.
 - c. In the Subsystem Type field, click the select button and then select the Subsystem Type from the dialog box and click OK.

The subsystem type that you select must have a check mark in the Is Named Enabled field.

- d. In the Description field, type a description of the named subsystem.
 - e. Click Menu, and then Save Record.
4. In the Profile Parameters list, modify the parameters as appropriate.

Parameters are added to the named subsystem, based on the specified subsystem type.

Related Topics

["About Siebel System Parameters" on page 4-2](#)

["About Named Subsystem Parameters" on page 4-6](#)

["Configuring the Siebel Enterprise Server" on page 4-7](#)

["Configuring Siebel Enterprise Server Named Subsystem Parameters" on page 4-11](#)

["Named Subsystem Management Commands"](#) on page 7-21

Configuring Siebel Enterprise Parameters

This topic describes how to configure Siebel Enterprise parameters.

To configure Siebel Enterprise parameters

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. Select the Parameters view tab.
3. In the Enterprise Parameters list, select the parameter of interest and configure its value.

Related Topics

["About Siebel System Parameters"](#) on page 4-2

["Configuring the Siebel Enterprise Server"](#) on page 4-7

Configuring Siebel Enterprise Component Definition Parameters

This topic describes how to configure Siebel Enterprise Server component definition parameters.

To configure Siebel Enterprise Server component definition parameters

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. Select the Component Definitions view tab.
3. In the Component Definitions list, select the Siebel Server component definition of interest.
4. In the Component Parameters list, make any changes to the component parameters.
5. If the component definition is based on a batch-mode component, then synchronize the component.
6. If a parameter value is effective at server restart, then restart the Siebel Server for changes to take effect.

The values of fixed parameters can be changed during component reconfiguration. Fixed parameters cannot be changed after the component has been activated or enabled.

Related Topics

["About Siebel System Parameters"](#) on page 4-2

["Configuring the Siebel Enterprise Server"](#) on page 4-7

["Synchronizing Components on a Siebel Enterprise Server"](#) on page 4-17

["About Siebel Server Component Definitions"](#) on page 4-22

["Reconfiguring Siebel Server Component Definitions"](#) on page 4-27

About System Alert Notification

System alert notification is a feature that allows a running server component to alert the administrator, using preconfigured communication channels, to any problems that cannot be handled by the server component.

The system alert notification process starts when a server component that has been configured for component notification encounters a problem. This component sends a request to the Siebel Administrator Notification component (alias AdminNotify) with details on the encountered problem and with an appropriate message to send to the administrator. The AdminNotify component then alerts the administrator by using the preconfigured communication channels, for example, email.

AdminNotify is a batch-mode, multithreaded server component and is part of the Auxiliary System Management (alias SystemAux) component group. This server component is enabled by default.

Some tasks involve configuring Siebel Server components for notification by using the Server Manager command-line interface.

Note the following points about system alert notification:

- A server component event or task event triggers a system alert notification.
- Losing database connectivity does not trigger a system alert notification.
- If a Siebel Server that hosts an AdminNotify server component is forced to shut down, then the AdminNotify server component also shuts down, resulting in the loss of the system alert notifications for server components or tasks on that Siebel Server.
- A server component or task on a Siebel Server cannot trigger an alert on an AdminNotify server component that is hosted by another Siebel Server in the Siebel Enterprise Server.
- A change in the state of a component (for example, from running to online) does not trigger a system alert notification.
- An administrator shutting down a server component does not trigger an alert.
- The server components required for the communications channel that delivers the system alert notification must be enabled.

Related Topics

["Configuring System Alert Notification"](#) on page 4-14

["Troubleshooting System Alert Notification"](#) on page 4-16

["System Alert Notification Commands"](#) on page 7-22

Configuring System Alert Notification

This topic describes how to configure system alert notification. It includes the following information:

- ["Creating a System Alert Profile"](#) on page 4-14
- ["Configuring Server Components to Use System Alerts"](#) on page 4-15

Creating a System Alert Profile

Use the following procedure for creating a system alert profile.

To create a system alert profile

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. Select the System Alerts view tab.
3. In the System Alerts view, click New to create a system alert profile record.
4. Enter values for system alert profile Name, Alias, and Description.
5. Click the Media column drop-down list and select the system alert notification medium.
6. Click Menu, and then Save Record.
7. In the Alert Parameters list, enter values to define the communication parameters. For example, define the email addresses and email server if the notification medium is by email notification.

Configuring Server Components to Use System Alerts

Use the following procedure for configuring server components to use system alerts by setting applicable server component parameters.

To configure components to use system alerts

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. Select the Component Groups view tab.
3. In the Component Groups list, select the Siebel Server component group of interest.
4. In the Components list, select the server component of interest.
5. In the Component Parameters list, query for and set the parameters described in the following table.

Parameter Name	Parameter Alias	Description
Notification Handler	NotifyHandler	The name of the system alert profile, which specifies the notification medium and settings for the component alerts. Set this value to the alias name of the system alert profile that you defined previously.
Disable Notification	DisableNotification	A Boolean value that enables or disables server component notification. The default value is False.
Time to Wait for doing Notification	NotifyTimeOut	Specifies the amount of time to wait in milliseconds for connecting to the named pipe, which is a system element used in notification communications. If the named pipe does not reply within the specified time, then the notification is terminated. The default value is 100 milliseconds.
Notification Action on Task Exit	NotifyOnTaskExit	An integer value that determines if notifications are sent in case of error. A value of 0 disables error notifications. A value of 1 enables error notifications. The default value is 0. Set this parameter to 1 to configure system alerts. Note: This parameter is an advanced parameter, which might not be set for display in the GUI.

Related Topics

- ["About Siebel System Parameters" on page 4-2](#)
- ["About Advanced and Hidden Parameters" on page 4-4](#)
- ["Configuring Siebel Enterprise Parameters" on page 4-13](#)
- ["About System Alert Notification" on page 4-14](#)
- ["Creating a System Alert Profile" on page 4-14](#)
- ["Troubleshooting System Alert Notification" on page 4-16](#)
- ["Configuring Siebel Server Parameters" on page 4-21](#)

Troubleshooting System Alert Notification

This topic provides guidelines for resolving problems with system alert notification. To resolve a problem, look for it in the list of symptoms or error messages in [Table 4-3](#).

For troubleshooting information about system alert notification, see [Table 4-3](#).

Table 4-3 Resolving System Alert Notification Problems

Problem	Cause	Solution
Not receiving system alerts	Incorrect enterprise, Siebel Server, or server component configurations	Review information in "Checking Your Siebel Enterprise and Siebel Server Configurations" on page 4-22.
	SMTP server defined in the system alert profile is not configured to accept requests from the Siebel Server	Review your SMTP server documentation to configure these requests.
	Review log files	Review log files of server component AdminNotify for other error messages or conditions. For information about configuring and reading server component log files, see <i>Siebel System Monitoring and Diagnostics Guide</i> .

Related Topics

- ["About System Alert Notification" on page 4-14](#)
- ["Configuring System Alert Notification" on page 4-14](#)
- ["Checking Your Siebel Enterprise and Siebel Server Configurations" on page 4-22](#)

Configuring Component Job Templates

This topic describes how to configure a component job template, which you can use on Siebel Servers across an enterprise. A component job template is a predefined component job that uses parameter values that you have defined. Use component job templates instead of individual component jobs if you are planning to regularly run component jobs with the same parameter values.

To define a component job template

1. Navigate to the Administration - Server Configuration screen, then the Job Templates view.
2. In the Job Templates list, click New.

3. In the Name field, type in a descriptive name for the component job, such as Monthly EIM.
4. In the Short Name field, type in an alias for the component job, such as MonthEIM.
5. In the Component field, select the component for this component job, such as Enterprise Integration Manager.

Note: After a component job is created, do not change the value of the Component field. To change the component for an existing component job, create a new component job instead of modifying the existing one.

6. In the Description field, type in a description of the component job.
7. Click Menu, and then Save Record.
8. In the Job Parameters list, click New.
9. In the Name field, select the parameter that you want to define for this component job.
 - a. In the Name field, click the select button.
The Component Parameters dialog box appears. The parameters that appear in the Component Parameters dialog box vary depending on the component that you specified in Step 5.
 - b. In the Component Parameters dialog box, click Query.
 - c. In the Name field, type in the name of the parameter and click Go.
 - d. If the query matches the parameter of interest, then click OK.
10. In the Value field of the Job Parameters list, type in the value for the parameter.
The default value is automatically displayed in this field.
11. Check the appropriate flags for this parameter. To set the parameter type, use the following flags:
 - For a fixed parameter, check the Fixed field.
 - For a required parameter, check the Required field.
12. Click Menu, and then Save Record.
13. Continue to choose parameters by completing Step 8 through Step 12 until you have defined the parameters for the component job.

Related Topics

["Configuring the Siebel Enterprise Server"](#) on page 4-7

["Administering Component Jobs"](#) on page 6-5

Synchronizing Components on a Siebel Enterprise Server

This topic describes how to synchronize components on a Siebel Enterprise Server. You must synchronize batch-mode Siebel Server components between the Siebel Gateway and the database whenever you:

- Create new component definitions

- Modify existing batch mode component definitions
- Delete Siebel Server components

Note: If synchronization does not take place, then make sure that the LOV (List of Value) type SRM_ACTION_TYPE is set to active. For more information about working with LOVs, see *Siebel Applications Administration Guide*.

To synchronize components on a Siebel Enterprise Server

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. Select the Synchronize view tab.
A list of batch-mode server components appears.
3. Click Synchronize.
This operation might take up to a minute to execute.
4. For the changes to take effect, stop and restart the Siebel Server system service.

Related Topics

["Configuring the Siebel Enterprise Server"](#) on page 4-7

["Administering the Siebel Server System Service"](#) on page 5-7

Configuring the Siebel Server

This topic lists the configuration tasks and processes applicable to the Siebel Server. For more information about the Siebel Server and the overall system architecture, see [Chapter 2, "Siebel Enterprise Server Architecture."](#)

This topic contains the following information:

- ["Enabling Component Groups on a Siebel Server"](#) on page 4-18
- ["Disabling Component Groups on a Siebel Server"](#) on page 4-19
- ["About Starting Siebel Server Components"](#) on page 4-19
- ["Automatically Starting a Component on a Siebel Server"](#) on page 4-20
- ["Manually Starting or Disabling a Component on a Siebel Server"](#) on page 4-21
- ["Configuring Siebel Server Parameters"](#) on page 4-21
- ["Configuring Siebel Server Component Parameters"](#) on page 4-21

Enabling Component Groups on a Siebel Server

This topic describes how to enable Siebel Server component groups on an individual Siebel Server.

When you initially configure a Siebel Server, you specify which component groups to enable. When you have to change which groups are enabled or disabled, use the procedures described in this topic and the topic that follows. For more information about the initial configuration tasks for the Siebel Server, see the *Siebel Installation Guide* for the operating system you are using.

To enable a component group on a Siebel Server

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. Select the Component Groups view tab.
3. In the Component Groups list, select the Siebel Server component group of interest.
4. In the Component Groups Assignments list, select the Siebel Server of interest.
5. Click Enable.
The Enabled on Server? field of the Siebel Server record becomes checked.
6. For the change to take effect, stop and restart the Siebel Server system service.

Related Topics

["About Enabled and Disabled Component Groups"](#) on page 4-10

["Enabling Component Groups on a Siebel Enterprise Server"](#) on page 4-11

["Configuring the Siebel Server"](#) on page 4-18

["Administering the Siebel Server System Service"](#) on page 5-7

Disabling Component Groups on a Siebel Server

This topic describes how to disable Siebel Server component groups on an individual Siebel Server.

To disable a component group on a Siebel Server

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. Select the Component Groups view tab.
3. In the Component Groups list, select the Siebel Server component group of interest.
4. In the Component Groups Assignments list, select the Siebel Server of interest.
5. Click Disable.
The Enabled on Server? field of the Siebel Server record becomes clear.
6. For the change to take effect, stop and restart the Siebel Server system service.

Related Topics

["About Enabled and Disabled Component Groups"](#) on page 4-10

["Disabling Component Groups on a Siebel Enterprise Server"](#) on page 4-11

["Configuring the Siebel Server"](#) on page 4-18

["Administering the Siebel Server System Service"](#) on page 5-7

About Starting Siebel Server Components

When a component group is enabled, all of the server components within the component group are started and assigned to the Siebel Servers. The Siebel Servers are configured to use the component group provided that the server components are

configured to start automatically. If the server components are not configured to start automatically, then you must start them manually.

You determine the state of a server component by viewing the value that appears in the State field for a component. This field is available, for example, when you choose Administration - Server Management, then Enterprises. The State field for a component can have one of the following possible values:

- **Running.** The server component is online and accepting requests, and at least one task is running.
- **Online.** The server component is online and awaiting a request.
 - For a multithreaded component, if the number of active running processes are greater than the value of the parameter MinMTServers, and no tasks are running for the component, then the state is Online.
 - For a background mode component, if the number of active running processes is less than the value of the parameter DfltTasks, and no tasks are running for the component, then the state is Online.
- **Not Online.** The server component is not online. After the Siebel Server is restarted, this component state might occur temporarily before the component's state becomes Online. If the status Not Online persists, then an error is preventing the component from becoming online. Check the component log and fix the error to let the component state become Online again.
- **Partially Offline.** The server component is partially offline and cannot start until the Siebel Server is restarted.
 - For a multithreaded component, if the number of active running processes is less than the value of the parameter MinMTServers, then the state is Partially Offline.
 - For a background mode component, if the number of active running processes is less than the value of the parameter DfltTasks, then the state is Partially Offline.
- **Unavailable.** The server component is unavailable.
- **Paused.** The server component is online but is not accepting new requests.
- **Shutting down.** The server component is shutting down and cannot accept new requests. At least one task is still running.
- **Shutdown.** The server component is shut down.

Related Topics

["Automatically Starting a Component on a Siebel Server" on page 4-20](#)

["Manually Starting or Disabling a Component on a Siebel Server" on page 4-21](#)

Automatically Starting a Component on a Siebel Server

This topic describes how to configure a Siebel Server component to start automatically when the Siebel Server starts.

To automatically start a component on a Siebel Server

1. Navigate to the Administration - Server Configuration screen, then the Servers view.
2. In the Siebel Servers list, select the Siebel Server of interest.

3. In the Components list, select the server component that you want to configure.
4. Click Auto Start.

The server component starts automatically when the Siebel Server starts.

Related Topics

["Configuring the Siebel Server" on page 4-18](#)

["About Starting Siebel Server Components" on page 4-19](#)

["Manually Starting or Disabling a Component on a Siebel Server" on page 4-21](#)

Manually Starting or Disabling a Component on a Siebel Server

This topic describes how to configure a Siebel Server component so that you must manually start it after the Siebel Server starts.

To manually start a component on a Siebel Server

1. Navigate to the Administration - Server Configuration screen, then the Servers view.
2. In the Siebel Servers list, select the Siebel Server of interest.
3. In the Components list, select the server component that you want to configure.
4. Click Manual Start.

The server component requires that you start it after the Siebel Server starts.

Related Topics

["Configuring the Siebel Server" on page 4-18](#)

["About Starting Siebel Server Components" on page 4-19](#)

["Automatically Starting a Component on a Siebel Server" on page 4-20](#)

Configuring Siebel Server Parameters

This topic describes how to configure Siebel Server parameters.

To configure Siebel Server parameters

1. Navigate to the Administration - Server Configuration screen, then the Servers view.
2. In the Siebel Servers list, select the Siebel Server of interest.
3. Select the Parameters view tab.
4. In the Parameters list, select the parameter of interest and configure its value.

Related Topics

["About Siebel System Parameters" on page 4-2](#)

["About Siebel Server Parameters" on page 4-5](#)

["Configuring the Siebel Server" on page 4-18](#)

Configuring Siebel Server Component Parameters

This topic describes how to configure Siebel Server component parameters.

To configure Siebel Server component parameters

1. Navigate to the Administration - Server Configuration screen, then the Servers view.
2. In the Siebel Servers list, select the Siebel Server of interest.
3. Click the Components view tab.
4. In the Components list, select the Siebel Server component of interest.
5. Select the Parameters view tab below the Components list.
6. In the Component Parameters list, select the parameter of interest and configure its value.

Related Topics

["About Siebel System Parameters"](#) on page 4-2

["About Siebel Component Parameters"](#) on page 4-5

["Configuring the Siebel Server"](#) on page 4-18

Checking Your Siebel Enterprise and Siebel Server Configurations

One of the main objectives of your Siebel Enterprise and Siebel Server configurations is to make sure that server components are properly configured and ready to execute tasks. Check the following bullet list to make sure that you meet the necessary configuration conditions for this objective:

- The component group that contains the server component member is enabled at the enterprise level.
- The component group that contains the server component is enabled at the Siebel Server level.
- The component definition is enabled. The component definition defines the configured component for the Siebel Enterprise and for all of its Siebel Servers.

If the previously listed conditions are true, then the Siebel Server allocates resources (some space in the shared memory and a public port) for the server component to use when the Siebel Server starts. The Siebel Server also marks the server component as ready (available) to start new tasks and performs any additional steps necessary, for example, starting shells if the server component is multithreaded. The number of multithreaded shells started is governed by the parameter Minimum MT Servers (alias MinMTServers). If the server component is a background mode component, then it starts the background number of tasks governed by the parameter Default Tasks (alias DfltTasks).

Related Topics

["Enabling Component Groups on a Siebel Enterprise Server"](#) on page 4-11

["Enabling Component Groups on a Siebel Server"](#) on page 4-18

["Activating a Custom Siebel Server Component Definition"](#) on page 4-25

About Siebel Server Component Definitions

If you want to use customized components, then you can create defined components or customize existing components. After it is defined, a component can have one of three definition states: Creating, Active, or Inactive.

- **Creating.** Indicates that the defined component is being configured. After the definition is configured, activating the component definition fixes its configuration, changes the component's state to Active, and allows the component to be assigned to Siebel Servers. The fixed parameters for the defined component cannot be overridden when the component is assigned, or when tasks are started for the component.
- **Active.** Indicates that the defined component definition state is available for registration on Siebel Servers.
- **Inactive.** Indicates that the defined component will be inactivated when you restart the Siebel Server (or servers) to which the component is assigned. The component remains assigned to the Siebel Servers, but tasks cannot be started for the component until you revert the component definition state to Active and restart the Siebel Servers.

Parameter values in a component definition are used to initialize the component on a specific Siebel Server.

Note: If component definitions are created, modified, or deleted for batch-mode components, then it is necessary to synchronize the components with the Siebel Gateway.

Related Topics

["Configuring Siebel Enterprise Component Definition Parameters"](#) on page 4-13

["Synchronizing Components on a Siebel Enterprise Server"](#) on page 4-17

["Process of Creating a Custom Siebel Server Component"](#) on page 4-23

["Deleting a Siebel Server Component Definition"](#) on page 4-26

["Deactivating a Siebel Server Component Definition"](#) on page 4-26

Process of Creating a Custom Siebel Server Component

This topic describes the process of creating a custom Siebel Server component.

To create a custom Siebel Server component

1. (Optional) Create a new component group.

Do not perform this task if you plan to add the new custom Siebel Server component to an existing component group. For information about this task, see ["Creating a Custom Siebel Server Component Group"](#) on page 4-24.

2. Create a new component definition.

For information about this task, see ["Creating a Custom Siebel Server Component Definition"](#) on page 4-24.

3. Activate the new component definition.

For information about this task, see ["Activating a Custom Siebel Server Component Definition"](#) on page 4-25.

4. Synchronize components if the new custom Siebel Server component is a batch-mode component.

For information about this task, see ["Synchronizing Components on a Siebel Enterprise Server"](#) on page 4-17.

5. Stop and restart the Siebel Server system service.

For information about this task, see ["Administering the Siebel Server System Service"](#) on page 5-7.

Related Topics

["About Siebel Server Component Definitions"](#) on page 4-22

["Deleting a Siebel Server Component Definition"](#) on page 4-26

["Deactivating a Siebel Server Component Definition"](#) on page 4-26

Creating a Custom Siebel Server Component Group

If you want to create your own defined components and assign them to component groups other than the predefined ones, then you first must create component groups before creating the defined components. Component groups allow you to run related tasks and administer related components in logical groupings. Do not perform this task if you plan to add a new custom Siebel Server component to an existing component group.

This task is an optional step in ["Process of Creating a Custom Siebel Server Component"](#) on page 4-23.

To create a custom component group

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. Select the Component Groups view tab.
3. In the Component Groups list, click New.
4. In the Name field, type in a name for the component group.

The name must be unique across the Siebel Enterprise Server. Specify a name that expressively identifies the component group.

5. In the Alias field, type in an alias for the component group.

The component group alias must:

- Be unique across the Siebel Enterprise Server
- Not contain any spaces

The maximum alias length is dependent on the operating system.

6. In the Description field, enter a description of the component group.
7. Click Menu, and then Save Record.

Creating a Custom Siebel Server Component Definition

This topic describes how to create a custom Siebel Server component definition. Each custom server component definition is based on a Siebel Server component type.

This task is a step in ["Process of Creating a Custom Siebel Server Component"](#) on page 4-23.

To create a custom Siebel Server component definition

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.

2. Select the Component Definitions view tab.
3. In the Component Definitions list, click Menu, and then New Record.
4. In the Component field, type in a name for the component.
The component name must:
 - Be unique across Siebel Enterprise Servers
 - Expressively identify the defined component
 - Not contain any numbers
5. In the Alias field, type in an alias for the component.
The component alias must:
 - Be unique across Siebel Enterprise Servers
 - Not contain any spaces
 The maximum alias length is dependent on the operating system.
6. In the Component Type field, click the select button and choose the component type that you want to use as the template for this component.
7. In the Description field, type in a description of this component.
8. In the Component Group field, click the select button and choose the component group to which this component will belong.
The group must exist before you can select it.

Note: You cannot modify the specified component group after you modify the component record.

9. Click Menu, and then Save Record.
The State field changes to Creating.
10. In the Component Parameters list, make any changes to the component parameters that were created.

The values of fixed parameters can be changed during component reconfiguration. Fixed parameters cannot be changed after you activate the component.

Related Topics

["About Siebel Server Component Definitions"](#) on page 4-22

["Reconfiguring Siebel Server Component Definitions"](#) on page 4-27

Activating a Custom Siebel Server Component Definition

This topic describes how to activate a custom Siebel Server component definition.

This task is a step in ["Process of Creating a Custom Siebel Server Component"](#) on page 4-23.

To activate a custom Siebel Server component definition

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. Select the Component Definitions view tab.

3. In the Component Definitions list, select the component definition of interest (that is not currently activated).
4. Click Activate.
The component definition state field changes to Active.
5. If the component definition is based on a batch-mode component, then synchronize the component.
6. For the change to take effect, stop and restart the Siebel Server system service.

Related Topics

["Synchronizing Components on a Siebel Enterprise Server"](#) on page 4-17

["About Siebel Server Component Definitions"](#) on page 4-22

["Administering the Siebel Server System Service"](#) on page 5-7

Deleting a Siebel Server Component Definition

This topic describes how to delete a Siebel Server component definition.

Caution: Make sure that no active server components use the component definition that you want to delete. If you are in doubt, then deactivate the component definition rather than delete it.

To delete a Siebel Server component definition

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. Select the Component Definitions view tab.
3. In the Component Definitions list, select the component definition of interest.
4. Click Delete.

Related Topics

["About Siebel Server Component Definitions"](#) on page 4-22

["Process of Creating a Custom Siebel Server Component"](#) on page 4-23

["Deactivating a Siebel Server Component Definition"](#) on page 4-26

Deactivating a Siebel Server Component Definition

This topic describes how to deactivate a custom Siebel Server component definition.

To deactivate a Siebel Server component definition

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. Select the Component Definitions view tab.
3. In the Component Definitions list, select the component definition of interest (that is currently activated).
4. Click Deactivate.

The State field for the component definition changes to Inactive.

5. For the change to take effect, stop and restart the Siebel Server system service.

Related Topics

["About Siebel Server Component Definitions"](#) on page 4-22

["Process of Creating a Custom Siebel Server Component"](#) on page 4-23

["Deleting a Siebel Server Component Definition"](#) on page 4-26

["Administering the Siebel Server System Service"](#) on page 5-7

Advanced Configuration Tasks

This topic lists advanced configuration tasks and processes applicable to the Siebel Enterprise Server and Siebel Server. For more information about the Siebel Server and the overall system architecture, see [Chapter 2, "Siebel Enterprise Server Architecture."](#)

For common configuration tasks for the Siebel Enterprise Server and Siebel Server, see:

- ["Configuring the Siebel Enterprise Server"](#) on page 4-7
- ["Configuring the Siebel Server"](#) on page 4-18

This topic contains the following:

- ["Reconfiguring Siebel Server Component Definitions"](#) on page 4-27
- ["Configuring Automatic Restart for Server Components"](#) on page 4-29
- ["Configuring Database Reconnect for Server Components"](#) on page 4-29
- ["Configuring Memory-Based Server Component Recycling"](#) on page 4-30
- ["Deleting System Parameter Overrides"](#) on page 4-31

Reconfiguring Siebel Server Component Definitions

Component reconfiguration is a process that allows existing component tasks to continue running until they finish, while starting new processes with reconfigured component parameter values. Each component can be reconfigured, but this task is primarily done for multithreaded components. This topic is part of ["Advanced Configuration Tasks"](#) on page 4-27.

Component reconfiguration is particularly useful for scenarios such as site migration. In this scenario, component reconfiguration allows you to maintain the existing component configuration, which remains available until the migration is complete and a new component configuration becomes available.

When a component reconfiguration is committed, this action signifies to every Siebel Server in the Siebel Enterprise Server that a new component definition is available and that new tasks should not start for that component. Existing tasks, however, continue to run until completion. The connected Siebel Servers then start new multithreaded processes for the component, using the new parameter values that were read from the Siebel Gateway. On each Siebel Server, the number of new multithreaded processes is governed by the parameter Minimum MT Servers (alias MinMTServers).

Previous component tasks that are not affected by the component reconfiguration can continue to run for some time. Therefore, the multithreaded processes hosting the tasks continue to run and the tasks occupy slots in shared memory. Because old and new multithreaded processes for the component are both running, there might be an increase in the number of multithreaded processes running on the Siebel Server computers.

Therefore, it is recommended that you run component definition reconfiguration at times when the server component workload is low, that is, when the component's existing tasks or sessions are few in number. Doing so allows the existing tasks or sessions on the old multithreaded processes to end, so that the total numbers of multithreaded processes and tasks do not exceed configured limits or exhaust system resources. When all of its tasks have ended, a multithreaded process eventually ends.

For each Siebel Server, initial sizing would have been performed, as described in *Siebel Performance Tuning Guide*. The total number of multithreaded processes for the component cannot exceed what is specified using the parameter Maximum MT Servers (alias MaxMTServers) and the total number of tasks cannot exceed what is specified using the parameter Maximum Tasks (alias MaxTasks).

Note: Parameters set at the individual component level are not affected by component definition reconfiguration unless the parameter override is deleted on that parameter.

Before reconfiguring Siebel Server components, make sure that:

- All of the Siebel Servers running the server component designated for reconfiguration are running. This check makes sure that the server component instances receive the reconfigured parameter values.
- Any external resources that are accessed by current tasks running on the existing component configuration remain available.

Examples of external resources include the configuration files that are defined in the component configuration.

- The Siebel runtime repository in effect reflects the application configuration you require.
- Any external resources that are defined in the new component configuration are available.
- Any previous component reconfiguration process has already completed. If it has not, then you might have to wait before you can reconfigure again.

If existing multithreaded processes are still running along with reconfigured multithreaded processes, then the following error message might appear: Unable to complete reconfiguration due to insufficient process resources. Starting another reconfiguration process at this time would require more reconfigured multithreaded processes on all applicable Siebel Servers, which might exceed the limits that you configured during sizing and tuning.

To reconfigure Siebel Server components

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. Select the Component Definitions view tab.
3. In the Component Definitions list, select the component definition that you want to reconfigure.
4. Click Menu, and then Start Reconfiguration.

The Definition State field changes to Reconfiguring.

5. In the lower Component Definitions list, change the Value field of parameters that you want to reconfigure for the component.

You can also change the values of fixed parameters, but you cannot change whether parameters are fixed.

6. After parameter values have been reconfigured, commit the new configuration by clicking Menu, and then Commit Reconfiguration.

The new parameter values are merged at the enterprise level. To cancel the reconfiguration before it has been committed, click Menu, and then Cancel Reconfiguration.

Related Topics

["Reconfiguring Component Definition Commands"](#) on page 7-16

Related Books

Siebel Performance Tuning Guide

Configuring Automatic Restart for Server Components

Automatic restart is a feature that allows a Siebel Server component to automatically attempt a restart if the component exits with an error. For a user-defined number of times after the error, the Siebel Server tries to restart the component. This feature greatly reduces the administration of Siebel Server components. By default, this feature is disabled for all components. This topic is part of ["Advanced Configuration Tasks"](#) on page 4-27.

Note: If a Siebel Server component is terminated, that is, it does not exit with an error, then the Siebel Server component is not restarted.

You can configure automatic restart by using the following parameters:

- Auto Restart (alias AutoRestart)
- Minimum Up Time (alias MinUpTime)
- Number of Restarts (alias NumRestart)

The Minimum Up Time and Number of Restarts parameters combine to determine the number of restart attempts in a time interval allowed for a component (NumRestart multiplied by MinUpTime). If a component instance cannot be restarted after this time interval, then no new restart is attempted (therefore, the component instance will not run).

Typically, you set these parameters at the component level, but, depending on your system configuration, you might want to set these parameters at the Siebel Enterprise Server or Siebel Server levels.

Related Topics

["About Siebel System Parameters"](#) on page 4-2

["Siebel Enterprise, Server, and Component Parameters"](#) on page A-11

Configuring Database Reconnect for Server Components

Database reconnect is an optional feature that enables Siebel Server components to automatically attempt a database connection following a database or network failure. At regular intervals after the failure, Siebel Server components try to reconnect to the database and resume any tasks that were rolled back due to the failure. This feature

greatly reduces the administration of Siebel Server components. This topic is part of ["Advanced Configuration Tasks"](#) on page 4-27.

Without database reconnect, a database or network failure causes the Siebel Server component to shut down and all of the running tasks to crash. You must then manually restart all of the components that were shut down and rerun all of the tasks that crashed.

Database reconnect is enabled for all of the background-mode and batch-mode Siebel Server components, except for the Enterprise Integration Manager and Database Extract components. This feature is disabled for all of the interactive-mode Siebel Server components (such as Synchronization Manager and all of the Application Object Manager components).

You can configure database reconnect by using the following parameters:

- Number of Retries (alias NumRetries)
- Retry Interval (alias RetryInterval)
- Retry Up Time (alias RetryUpTime)

Set these parameters at the same level as the automatic restart parameters (typically, at the component level).

Related Topics

["About Siebel System Parameters"](#) on page 4-2

["Configuring Automatic Restart for Server Components"](#) on page 4-29

["Siebel Enterprise, Server, and Component Parameters"](#) on page A-11

Configuring Memory-Based Server Component Recycling

If certain multithreaded server components within your Siebel application are experiencing excessive memory consumption, then you can configure certain parameters to configure a component process to restart automatically. This feature, called component recycling, allows continued operation of server components without affecting end users. This topic is part of ["Advanced Configuration Tasks"](#) on page 4-27.

The memory-based component recycling feature operates as follows:

- Identifies a process for recycling by monitoring virtual memory usage
- Flags the process not to accept any new requests
- Starts another process to take the place of the original process
- Waits for all of the current tasks to complete
- Shuts down the process, which releases memory resources back to the operating system

To configure memory-based recycling of server components, set the parameters Memory Usage Based Multithread Shell Recycling (alias MemoryBasedRecycle) and Process VM Usage Lower Limit (alias MemoryLimit) at the component level for the affected multithreaded server component. The parameter MemoryBasedRecycle allows the recycling feature to monitor the virtual memory of a process and begins the recycling procedure when a certain memory limit is reached. For example, on Windows, this virtual memory is the working set of a process. The parameter MemoryLimit sets the memory limit at which recycling occurs.

You can also set a value in percent for the parameter Process VM Usage Upper Limit (alias MemoryLimitPercent). The default value is 20. When memory usage exceeds the value of MemoryLimitPercent above MemoryLimit, a fast shutdown of the memory consuming process is triggered rather than a normal shutdown.

Set the parameters for memory-based server component recycling at the component level.

For a listing of preconfigured server components, see [Table A-2](#). This table indicates whether the server component is multithreaded and, therefore, eligible to use the memory-based recycling feature.

Related Topics

["Siebel Enterprise, Server, and Component Parameters"](#) on page A-11

["Generic Parameters"](#) on page A-18

Deleting System Parameter Overrides

As previously described, lower-level system parameters inherit values from the same higher-level system parameters. However, modifying a lower-level parameter value sets an override at this level. That is, the lower-level parameter loses the ability to inherit values from higher-level parameters. To reinstate the default functionality, perform a delete parameter override operation on affected parameters. This topic is part of ["Advanced Configuration Tasks"](#) on page 4-27.

The following procedures describe how to delete parameter overrides for Siebel Enterprise Server parameters, Siebel Server parameters, component definition parameters, and Siebel Server component parameters.

Deleting a Parameter Override for a Siebel Enterprise Parameter

This procedure describes how to delete a parameter override for a Siebel Enterprise parameter.

To delete a parameter override for a Siebel Enterprise parameter

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. Select the Parameters view tab.
3. In the Enterprise Parameters list, select the parameter of interest.
4. Click Menu, and then Delete Parameter Override.

Deleting a Parameter Override for a Siebel Server Parameter

This procedure describes how to delete a parameter override for a Siebel Server parameter.

To delete a parameter override for a Siebel Server parameter

1. Navigate to the Administration - Server Configuration screen, then the Servers view.
2. Select the Parameters view tab.
3. In the Server Parameters list, select the parameter of interest.
4. Click Menu, and then Delete Parameter Override.

Deleting a Parameter Override for a Component Definition Parameter

This procedure describes how to delete a parameter override for a component definition parameter.

To delete a parameter override for a component definition parameter

1. Navigate to the Administration - Server Configuration screen, then the Enterprises view.
2. Select the Component Definitions view tab.
3. In the Component Definitions list, select the component definition that you want to reconfigure.
4. Select the Parameters view tab.
5. In the Component Parameters list, select the parameter of interest.
6. Click Menu, and then Delete Parameter Override.

Deleting a Parameter Override for a Siebel Server Component Parameter

This procedure describes how to delete a parameter override for a Siebel Server component parameter.

To delete a parameter override for a Siebel Server component parameter

1. Navigate to the Administration - Server Configuration screen, then the Servers view.
2. Select the Components view tab.
3. Select the component of interest.
4. Click the Parameters view tab below the Components view tab.
5. In the Component Parameters list, select the parameter of interest.
6. Click Menu, and then Delete Parameter Override.

Related Topics

["About Siebel Server Parameters"](#) on page 4-5

Administering Server System Services

This chapter describes the sequence in which to start up and shut down your Siebel deployment, and provides the procedures required to start, stop, and administer the Siebel Gateway system service and the Siebel Server system service.

This chapter includes the following topics:

- [Starting and Shutting Down a Siebel CRM Deployment](#)
- [Administering the Siebel Gateway System Service](#)
- [Administering the Siebel Server System Service](#)

Starting and Shutting Down a Siebel CRM Deployment

It is important to follow the correct sequence when starting or shutting down a Siebel CRM deployment, because several dependencies require that certain servers are running before others. Perform the following procedures to start or shut down your Siebel CRM deployment.

This topic contains the following information:

- ["Starting a Siebel CRM Deployment" on page 5-1](#)
- ["Shutting Down a Siebel CRM Deployment" on page 5-2](#)

Starting a Siebel CRM Deployment

This procedure describes how to start a Siebel CRM deployment.

To start a Siebel CRM deployment

1. Start the Siebel database.
For more information about this task, see your database documentation.
2. Start the Siebel Gateway system service.
3. Start any third-party software, if applicable.
4. Start the Siebel Server system service.

The Siebel Server must connect to the Siebel Gateway and Siebel database on startup.

5. Start the application container for each applicable installed module. To do so, run one of the following commands:

Windows. Execute `SIEBEL_ROOT\applicationcontainer\bin\startup.bat`.

UNIX. Execute `SIEBEL_ROOT/applicationcontainer/bin/startup.sh`.

The application container is automatically started only once, after installation. Before you start the application container manually, verify that its process is not already running: javaw.exe on Windows or javaw on UNIX. For more information about stopping and starting the application container, see the *Siebel Installation Guide* for the operating system you are using.

Related Topics

["Administering the Siebel Gateway System Service"](#) on page 5-3

["Configuring Siebel Server Load Balancing"](#) on page 3-5

["Administering the Siebel Server System Service"](#) on page 5-7

Related Books

Siebel Deployment Planning Guide

Siebel Installation Guide for the operating system you are using

Siebel Security Guide

Shutting Down a Siebel CRM Deployment

This procedure describes how to shut down a Siebel CRM deployment.

To shut down a Siebel CRM deployment

1. Shut down the Siebel Server system service.

When the Siebel Server system service is shut down, it shuts down server components and tasks before shutting down itself.

Note: To make sure that server components shut down properly, shut down Siebel Servers before shutting down the Siebel Server system service.

2. Shut down the Siebel Gateway system service

Note: Make sure that all of the Siebel Servers are shut down before shutting down the Siebel Gateway service.

3. Shut down the application container for each applicable installed module. To do so, run one of the following commands:

Windows. Execute `SIEBEL_ROOT\applicationcontainer\bin\shutdown.bat`.

UNIX. Execute `SIEBEL_ROOT/applicationcontainer/bin/shutdown.sh`.

When you shut down the application container, verify that its process is not running: javaw.exe on Windows or javaw on UNIX. For more information about stopping and starting the application container, see the *Siebel Installation Guide* for the operating system you are using.

4. Shut down the Siebel database.

For more information about this task, see your database documentation.

Related Topics

["Administering the Siebel Gateway System Service"](#) on page 5-3

["Administering the Siebel Server System Service"](#) on page 5-7

["Shutting Down a Siebel Server"](#) on page 6-2

["Siebel Server Manager Commands"](#) on page 7-5

Related Books

Siebel Deployment Planning Guide

Siebel Installation Guide for the operating system you are using

Administering the Siebel Gateway System Service

The Siebel Gateway authenticates any client attempting to access configuration information. You set up the method of authentication during initial configuration.

Occasionally, you must stop and restart the Siebel Gateway system service for maintenance purposes. Restart the system service only when it is necessary.

Administering the Siebel Gateway also sometimes requires you to start or stop the application container manually, as described in ["Starting a Siebel CRM Deployment"](#) on page 5-1 and ["Shutting Down a Siebel CRM Deployment"](#) on page 5-2. See also the *Siebel Installation Guide* for the operating system you are using.

Note: For compatibility with previous releases, the actual name of the system service is Siebel Gateway Name Server. However, this guide refers instead to Siebel Gateway, for consistency with current usage.

This topic includes the following information:

- ["About Siebel Gateway Authentication"](#) on page 5-3
- ["Administering the Siebel Gateway System Service on Windows"](#) on page 5-4
- ["Administering the Siebel Gateway System Service on UNIX"](#) on page 5-5

Related Topics

["About the Siebel Gateway"](#) on page 2-2

Related Books

Siebel Installation Guide for the operating system you are using

Siebel Security Guide

About Siebel Gateway Authentication

This topic provides an overview of Siebel Gateway authentication. All of the server and client side executable programs that connect to the Siebel Gateway, including the Siebel Server, pass a user name and password to the Siebel Gateway for authentication.

Configuration of Siebel Gateway authentication is part of initial configuration using Siebel Management Server. No additional configuration is required, unless, for instance, you change a data source, or choose to use a different means of authentication than that specified during initial configuration. For more information, see the *Siebel Installation Guide* for the operating system you are using. This topic is part of ["Administering the Siebel Gateway System Service"](#) on page 5-3.

Administering the Siebel Gateway System Service on Windows

This topic describes how to start, stop, and check the status of the Siebel Gateway system service on Windows. This topic is part of "[Administering the Siebel Gateway System Service](#)" on page 5-3.

Starting the Siebel Gateway System Service on Windows

This procedure describes how to start the Siebel Gateway system service on Windows.

To start the Siebel Gateway system service on Windows

1. Right-click My Computer.
2. Click Manage.
The Computer Management panel appears.
3. In the Computer Management tree, expand Services and Applications.
4. Click Services.
5. In the details panel, scroll through the list of services and select Siebel Gateway Name Server.
6. Right-click Siebel Gateway Name Server and select Start.
Windows starts the Siebel Gateway Name Server system service. This operation might take a few seconds. After the service has started, the Status field changes to Started.
7. Open the Task Manager and check whether the javaw.exe process for the application container is running.
If you need to start the application container manually, do so as described in "[Starting a Siebel CRM Deployment](#)" on page 5-1.

Stopping the Siebel Gateway System Service on Windows

This procedure describes how to stop the Siebel Gateway system service on Windows.

To stop the Siebel Gateway system service on Windows

1. Right-click My Computer.
2. Click Manage.
The Computer Management panel appears.
3. In the Computer Management tree, expand Services and Applications.
4. Click Services.
5. In the details panel, scroll through the list of services and select Siebel Gateway Name Server.
6. Right-click Siebel Gateway Name Server and select Stop.
The Stop Other Services dialog box now appears and asks whether you want to stop the Siebel Server system service.
7. Click Yes.
Windows stops the Siebel Gateway Name Server system service. This operation might take a few seconds. After the service has stopped, the Status field is blank.
8. Open the Task Manager and check whether the javaw.exe process for the application container is running.

If you need to stop the application container manually, do so as described in ["Shutting Down a Siebel CRM Deployment"](#) on page 5-2.

Checking the Status of the Siebel Gateway System Service on Windows

This procedure describes how to check the status of the Siebel Gateway system service on Windows.

To check the status of the Siebel Gateway system service on Windows

1. Right-click My Computer.
2. Click Manage.
The Computer Management panel appears.
3. In the Computer Management tree, expand Services and Applications.
4. Click Services.
5. In the details panel, scroll through the list of services and select Siebel Gateway Name Server.

A value of Started in the Status field for the specified service indicates that the Siebel Gateway Name Server system service is running. If the Status field is blank, then the system service is not currently running.

6. Open the Task Manager and check whether the javaw.exe process for the application container is running.

If you need to start or stop the application container manually, do so as described in ["Starting a Siebel CRM Deployment"](#) on page 5-1 or ["Shutting Down a Siebel CRM Deployment"](#) on page 5-2.

Administering the Siebel Gateway System Service on UNIX

This topic describes how to start, stop, and check the status of the Siebel Gateway system service on UNIX. This topic is part of ["Administering the Siebel Gateway System Service"](#) on page 5-3.

Starting the Siebel Gateway System Service on UNIX

This procedure describes how to start the Siebel Gateway system service on UNIX.

To start the Siebel Gateway system service on UNIX

1. Log in as the Siebel Service owner user.
2. Run the siebenv.sh or siebenv.csh script to set Siebel environment variables. For more information about these scripts, see *Siebel Installation Guide for UNIX*.
3. Enter the following command:

```
start_ns
```

With some of the available command-line flags, you can do the following:

- To specify the Siebel root directory, use the -r flag, as follows:

```
start_ns -r siebel_root
```

Typically, you do not have to use this flag, because the SIEBEL_ROOT environment variable is set by the siebenv.csh (or siebenv.sh) script. If the variable is not set, then you must specify the Siebel root directory to indicate the Siebel installation under which the Siebel Gateway runs.

- To start the Siebel Gateway only if currently marked with the autostart attribute, use the `-a` flag, as follows:

```
start_ns -a
```

Typically, use this flag only when invoking the `start_ns` script from an autostart script. For more information about the autostart script, see *Siebel Installation Guide for UNIX*.

- To force the startup, use the `-f` flag, as follows:

```
start_ns -f
```

This command can be used to make sure that the Siebel Gateway starts even if it was not previously shut down completely. This flag is typically not needed.

4. Run the `ps` command and check whether the `javaw` process (daemon) is running. If you need to start the application container manually, do so as described in ["Starting a Siebel CRM Deployment"](#) on page 5-1.

Stopping the Siebel Gateway System Service on UNIX

This procedure describes how to stop the Siebel Gateway system service on UNIX.

To stop the Siebel Gateway system service on UNIX

1. Log in as the Siebel Service owner user.
2. Run the `siebenv.sh` script in the current shell process, as follows:

```
./siebenv.sh
```

3. Enter the following command:

```
stop_ns -r siebel_root -f
```

With some of the available command-line flags, you can do the following:

- To specify the Siebel root directory, use the `-r` flag, as follows:

```
stop_ns -r siebel_root
```

Typically, you do not have to use this flag, because the `SIEBEL_ROOT` environment variable is set by the `siebenv.csh` (or `siebenv.sh`) script. If the variable is not set, then you must specify the Siebel root directory to indicate the Siebel installation under which the Siebel Gateway is running.

- To force the shutdown, use the `-f` flag, as follows:

```
stop_ns -f
```

This flag causes the Siebel Gateway to shut down sooner, but it might not shut down completely. In general, use the `-f` flag only if the Siebel Gateway did not respond to the unforced shutdown in a timely manner.

4. Run the `ps` command and check whether the `javaw` process (daemon) is running. If you need to stop the application container manually, do so as described in ["Shutting Down a Siebel CRM Deployment"](#) on page 5-2.

Checking the Status of the Siebel Gateway System Service on UNIX

This procedure describes how to check the status of the Siebel Gateway system service on UNIX.

To check the status of the Siebel Gateway system service on UNIX

1. Enter the following command:

```
list_ns
```

To specify the Siebel root directory, use the `-r` flag, as follows:

```
list_ns -r siebel_root
```

Typically, you do not have to use this flag, because the `SIEBEL_ROOT` environment variable is set by the `siebenv.csh` (or `siebenv.sh`) script. If the variable is not set, then you must specify the Siebel root directory to indicate the Siebel installation under which the Siebel Gateway is configured.

2. Run the `ps` command and check whether the `javaw` process is running.

If you need to start or stop the application container manually, do so as described in ["Starting a Siebel CRM Deployment"](#) on page 5-1 or ["Shutting Down a Siebel CRM Deployment"](#) on page 5-2.

Administering the Siebel Server System Service

Occasionally, you must stop and restart the Siebel Server system service for certain administrative changes to take effect. Restart the system service only when it is necessary.

Note: The Siebel Server system service must be running before any Siebel Server can be started.

Administering the Siebel Server also sometimes requires you to start or stop the application container manually, as described in ["Starting a Siebel CRM Deployment"](#) on page 5-1 and ["Shutting Down a Siebel CRM Deployment"](#) on page 5-2. See also the *Siebel Installation Guide* for the operating system you are using.

This topic includes the following information:

- ["Administering the Siebel Server System Service on Windows"](#) on page 5-7
- ["Administering the Siebel Server System Service on UNIX"](#) on page 5-9

Related Topics

["About the Siebel Server System Service"](#) on page 2-4

Related Books

Siebel Installation Guide for the operating system you are using

Administering the Siebel Server System Service on Windows

This topic describes how to start, stop, and check the status of the Siebel Server system service on Windows. This topic is part of ["Administering the Siebel Server System Service"](#) on page 5-7.

Starting the Siebel Server System Service on Windows

This procedure describes how to start the Siebel Server system service on Windows.

To start the Siebel Server system service on Windows

1. Right-click My Computer.
2. Click Manage.
The Computer Management panel appears.
3. In the Computer Management tree, expand Services and Applications.
4. Click Services.
5. In the details panel, scroll through the list of services and select the Siebel Server system service that you need (the enterprise name and Siebel Server name are indicated within square brackets).
6. Right-click the Siebel Server system service and select Start.
Windows starts the Siebel Server system service. This operation might take a few seconds. After the service has started, the Status field changes to Started.

Stopping the Siebel Server System Service on Windows

This procedure describes how to stop the Siebel Server system service on Windows.

To stop the Siebel Server system service on Windows

1. Right-click My Computer.
2. Click Manage.
The Computer Management panel appears.
3. In the Computer Management tree, expand Services and Applications.
4. Click Services.
5. In the details panel, scroll through the list of services and select the Siebel Server system service that you need (the enterprise name and Siebel Server name are indicated within square brackets).
6. Right-click the Siebel Server system service and select Stop.
Windows stops the Siebel Server system service. This operation might take a few seconds. After the service has stopped, the Status field is blank.

Note: A Microsoft Windows 1053 error might occur during this process. This error does not prevent the Siebel Server system service from stopping.

Checking the Status of the Siebel Server System Service on Windows

This procedure describes how to check the status of the Siebel Server system service on Windows.

To check the status of the Siebel Server system service on Windows

1. Right-click My Computer.
2. Click Manage.
The Computer Management panel appears.
3. In the Computer Management tree, expand Services and Applications.
4. Click Services.

5. In the details panel, scroll through the list of services and select the Siebel Server system service that you need (the enterprise name and Siebel Server name are indicated within square brackets).

A value of Started in the Status field for the specified service indicates that the system service is running for the Siebel Server. If the Status field is blank, then the system service is not currently running.

Administering the Siebel Server System Service on UNIX

This topic describes how to start, stop, check, and reset the Siebel Server system service daemon process on UNIX. This topic is part of "[Administering the Siebel Server System Service](#)" on page 5-7.

Starting the Siebel Server System Service on UNIX

This procedure describes how to start the Siebel Server system service on UNIX.

To start the Siebel Server system service on UNIX

1. Log in as the Siebel Service owner user.
2. Run the `siebenv.sh` or `siebenv.csh` script to set Siebel environment variables. For more information about these scripts, see *Siebel Installation Guide for UNIX*.
3. Enter the following command:

```
start_server siebel_server_name
```

In this command, `siebel_server_name` is the name of the Siebel Server.

You can run this script to start the system service for a specified Siebel Server (or servers), either within a specified Siebel Enterprise Server or across Siebel Enterprise Servers defined for the current installation.

- To start multiple servers, enter the names of the Siebel Servers (separated by spaces), or enter `all` to start all of the Siebel Servers configured under the specified `SIEBEL_ROOT` on the particular server computer (or all of the Siebel Servers for a particular Siebel Enterprise Server, if the Siebel Enterprise Server name is specified, as described in the use of the `-e` flag):

```
start_server server1 server2...
start_server all
```

- To specify the Siebel root directory, use the `-r` flag, as follows:

```
start_server -r siebel_root
```

Typically, you do not have to use this flag, because the `SIEBEL_ROOT` environment variable is set by the `siebenv.csh` (or `siebenv.sh`) script during initial configuration. If the variable is not set, then you must specify the Siebel root directory to indicate the Siebel installation under which the Siebel Server (or servers) run.

- To limit the operation to Siebel Servers in a specific Siebel Enterprise Server, use the `-e` flag, as follows:

```
start_server -e enterprise server1 server2...
```

You do not have to use this flag if the `SIEBEL_ENTERPRISE` environment variable is set in the `siebenv.csh` (or `siebenv.sh`) script during initial configuration. If the variable is not set, then you must specify the Siebel

Enterprise Server name. To start all of the servers for all of the Siebel Enterprise Servers configured for the SIEBEL_ROOT, do not use this flag (you might also have to unset the SIEBEL_ENTERPRISE environment variable).

For example, to start the Siebel Server system services for the prod01 server in the Siebel Enterprise Server, use a command like the following:

```
start_server -e siebel prod01
```

To start the Siebel Server system services for the prod01 and prod02 servers in the Siebel Enterprise Server, use a command like the following:

```
start_server -e siebel prod01 prod02
```

- To start only Siebel Servers that are marked with the autostart attribute, use the -a flag, as follows:

```
start_server -a
```

Typically, use this flag only when invoking the start_server script from an autostart script. For more information about the autostart script, see *Siebel Installation Guide for UNIX*.

- To force the startup, use the -f flag, as follows:

```
start_server -f
```

This flag can be used to make sure that the Siebel Server (or servers) start even if it was not previously shut down cleanly. This flag is typically not needed.

Note: Do not manually copy or rename the svc.siebsrvr.* filenames or any files in the *SIEBSRV_ROOT/sys* directory. Additionally, do not delete the MW* (mainwin) files stored in the /tmp directory while the Siebel Server is running. These files are reused by components in the event of a component restart.

Stopping the Siebel Server System Service on UNIX

This procedure describes how to stop the Siebel Server system service on UNIX.

To stop the Siebel Server system service on UNIX

1. Log in as the Siebel Service owner user.
2. Run the siebenv.sh script in the current shell process, as follows:

```
. ./siebenv.sh
```

3. Enter the following command:

```
stop_server siebel_server_name
```

You can run this script to stop the system service for a specified Siebel Server (or servers), either within a specified Siebel Enterprise Server or across all of the Siebel Enterprise Servers defined for the current installation.

- To stop multiple Siebel Servers, enter the names of the Siebel Servers (separated by spaces), or enter all to stop all of the Siebel Servers configured under the specified SIEBEL_ROOT (or all of the Siebel Servers for a particular Siebel Enterprise Server, if the Siebel Enterprise Server name is specified, as described in the use of the -e flag), as follows:

```
stop_server server1 server2...
stop_server all
```

- To specify the Siebel root directory, use the `-r` flag, as follows:

```
stop_server -r siebel_root
```

Typically, you do not have to use this flag, because the `SIEBEL_ROOT` environment variable is set by the `siebenv.csh` (or `siebenv.sh`) script during initial configuration. If the variable is not set, then you must specify the Siebel root directory to indicate the Siebel installation under which the Siebel Server (or servers) is running.

- To limit the operation to Siebel Servers in a specific Siebel Enterprise Server, use the `-e` flag, as follows:

```
stop_server -e enterprise server1 server2...
```

You do not have to use this flag if the `SIEBEL_ENTERPRISE` environment variable is set in the `siebenv.csh` (or `siebenv.sh`) script during initial configuration. If the variable is not set, then you must specify the Siebel Enterprise Server name. To stop all of the Siebel Servers for all of the Siebel Enterprise Servers configured for the `SIEBEL_ROOT`, do not use this flag (you might have to unset the `SIEBEL_ENTERPRISE` environment variable).

To stop the Siebel Server system service for the `prod01` server in the Siebel Enterprise Server, use a command like the following:

```
stop_server -e siebel prod01
```

- To force the shutdown, use the `-f` flag, as follows:

```
stop_server -f
```

This flag causes the Siebel Server to shut down sooner, but might not give all of the components a chance to shut down cleanly. In general, use the force option only if the Siebel Servers did not respond to the unforced shutdown in a timely manner.

Note: A normal shutdown of the Siebel Server system service on UNIX deletes MainWin page files of the format `MW*` stored in the `/tmp` directory. You can safely delete these files if they remain after the Siebel Server shuts down. However, do not delete these files while the Siebel Server is running.

Resetting the Siebel Server System Service on UNIX

This procedure describes how to reset the Siebel Server system service on UNIX.

To reset the Siebel Server system service on UNIX

- Enter the following command:

```
reset_server siebel_server_name
```

Note: Use this script only if the Siebel Server system service is unable to start after an abnormal shutdown or crash of the Siebel Server computer. Do not use it as part of the normal operation of the Siebel Server.

You can run this script to reset the system service for a specified Siebel Server (or servers), either within a specified Siebel Enterprise Server or across all of the Siebel Enterprise Servers defined for the current installation. The names of one or more Siebel Servers (separated by spaces) must be specified on the command line.

- To reset multiple Siebel Servers, enter the names of the Siebel Servers (separated by spaces), or enter `all` to reset all of the Siebel Servers configured under the specified `SIEBEL_ROOT` (or all of the Siebel Servers for a particular Siebel Enterprise Server, if the Siebel Enterprise Server name is specified, as described in the use of the `-e` flag), as follows:

```
reset_server server1 server2...  
reset_server all
```

- To specify the Siebel root directory, use the `-r` flag, as follows:

```
reset_server -r siebel_root
```

Typically, you do not have to use this flag, because the `SIEBEL_ROOT` environment variable is set by the `siebenv.csh` (or `siebenv.sh`) script during initial configuration. If the variable is not set, then you must specify the Siebel root directory to indicate the Siebel installation under which the Siebel Server (or servers) is running.

- To specify the Siebel Enterprise Server under which the specified Siebel Server (or servers) is configured, use the `-e` flag, as follows:

```
reset_server -e enterprise server1 server2...
```

You do not have to use this flag if the `SIEBEL_ENTERPRISE` environment variable is set in the `siebenv.csh` (or `siebenv.sh`) script during initial configuration. If the variable is not set, then you must specify the Siebel Enterprise Server name to indicate the Siebel Enterprise Server under which the Siebel Servers are configured. To reset all of the Siebel Servers for all of the Siebel Enterprise Servers configured for the `SIEBEL_ROOT`, use `all` for the `enterprise` variable.

To reset the Siebel Server system service for the `prod01` server in the Siebel Enterprise Server, use a command like the following:

```
reset_server -e siebel prod01
```

Administering Siebel Server Run-Time Operations

This chapter describes Siebel Server run-time administration tasks and processes performed by using the Siebel Server Manager GUI. It includes the following topics:

- [Administering Siebel Servers](#)
- [Administering Siebel Server Component Groups](#)
- [Administering Siebel Server Components](#)
- [Administering Component Jobs](#)
- [Administering Siebel Server Tasks](#)

Administering Siebel Servers

This topic lists the administration tasks applicable to Siebel Servers. It includes the following information:

- ["Starting a Siebel Server" on page 6-1](#)
- ["Shutting Down a Siebel Server" on page 6-2](#)

Related Topics

[Chapter 2, "Siebel Enterprise Server Architecture"](#)

["Administering the Siebel Server System Service" on page 5-7](#)

Related Books

Siebel System Monitoring and Diagnostics Guide

Starting a Siebel Server

This topic describes how to start a Siebel Server.

Note: In order to start the Siebel Server, the Siebel Server system service must be running.

If the Auto Startup Mode (alias AutoStart) Siebel Server parameter is set to the default value of True, then the Siebel Server starts automatically when the Siebel Server system service is started.

Note: Starting a Siebel Server starts the default number of tasks, as defined in the Default Tasks (alias DfltTasks) parameter, for each background-mode component.

This topic is part of "[Administering Siebel Servers](#)" on page 6-1.

To start a Siebel Server

1. Navigate to Administration - Server Management screen, then the Enterprises view.
2. In the Servers list, select the Siebel Server of interest.
3. Click Startup.

The State field changes to Starting Up.

Shutting Down a Siebel Server

This topic describes how to shut down a Siebel Server.

Caution: If you shut down the Siebel Server that is hosting your current Siebel Web Client session, then you lose connection to the Siebel Server and cannot restart the Siebel Server by using the Siebel Web Client. In such a case, you must restart the Siebel Server by using the Siebel Developer Web Client or the Server Manager command-line interface. You can shut down and restart Siebel Servers that do not host your Siebel Web Client session without losing your connection.

This topic is part of "[Administering Siebel Servers](#)" on page 6-1.

To shut down a Siebel Server

1. Navigate to Administration - Server Management screen, then the Enterprises view.
2. In the Servers list, select the Siebel Server of interest.
3. Click Shutdown.

The State field changes to Shutting Down.

Note: Shutting down the Siebel Server does not automatically shut down the Siebel Server system service. In some cases, you must shut down not only the Siebel Server, but also the Siebel Server system service.

Administering Siebel Server Component Groups

This topic lists the administration tasks applicable to component groups on a Siebel Server. Enabling or disabling a server component group makes all of the components within the component group available or unavailable.

This topic includes the following information:

- "[Enabling a Component Group on a Siebel Server](#)" on page 6-3
- "[Disabling a Component Group on a Siebel Server](#)" on page 6-3

Related Topics

[Chapter 2, "Siebel Enterprise Server Architecture"](#)

Enabling a Component Group on a Siebel Server

This topic describes how to enable a component group on a Siebel Server.

This topic is part of "[Administering Siebel Server Component Groups](#)" on page 6-2.

To enable a component group on a Siebel Server

1. Navigate to Administration - Server Configuration screen, then the Enterprises view.
2. In the Enterprise Servers list, select the enterprise of interest.
3. In the Component Group list, select the component group of interest (that is currently disabled).
4. Click Enable.

The Enable State field of the component group record changes to Enabled.

Related Topics

["Disabling a Component Group on a Siebel Server"](#) on page 6-3

Disabling a Component Group on a Siebel Server

This topic describes how to disable a component group on a Siebel Server.

This topic is part of "[Administering Siebel Server Component Groups](#)" on page 6-2.

To disable a component group on a Siebel Server

1. Navigate to Administration - Server Configuration screen, then the Enterprises view.
2. In the Enterprise Servers list, select the enterprise of interest.
3. In the Component Group list, select the component group of interest (that is currently enabled).
4. Click Disable.

The Enable State field of the component group record changes to Disabled.

Related Topics

["Enabling a Component Group on a Siebel Server"](#) on page 6-3

Administering Siebel Server Components

This topic lists the administration tasks applicable to Siebel Server components. It includes the following information:

- ["Starting a Server Component on a Siebel Server"](#) on page 6-4
- ["Shutting Down a Server Component on a Siebel Server"](#) on page 6-4
- ["Recovering an Unavailable Server Component"](#) on page 6-4
- ["Pausing Server Components on a Siebel Server"](#) on page 6-5
- ["Resuming Server Components on a Siebel Server"](#) on page 6-5

Related Topics

["About Starting Siebel Server Components"](#) on page 4-19

[Chapter 2, "Siebel Enterprise Server Architecture"](#)

Starting a Server Component on a Siebel Server

This topic describes how to start a server component on a Siebel Server.

This topic is part of ["Administering Siebel Server Components"](#) on page 6-3.

To start a server component on a Siebel Server

1. Navigate to Administration - Server Management screen, then the Components view.
2. In the Components list, select the server component of interest.

Note: Make sure that you select the server component on the Siebel Server of interest.

3. Click Startup.

Shutting Down a Server Component on a Siebel Server

This topic describes how to shut down a server component on a Siebel Server.

This topic is part of ["Administering Siebel Server Components"](#) on page 6-3.

To shut down a server component on a Siebel Server

1. Navigate to Administration - Server Management screen, then the Components view.
2. In the Components list, select the server component of interest.

Note: Make sure that you select the server component on the Siebel Server of interest.

3. Click Shutdown.

Recovering an Unavailable Server Component

This topic describes how to recover a server component that has an Unavailable state.

This topic is part of ["Administering Siebel Server Components"](#) on page 6-3.

To recover a server component from an unavailable component state

1. Navigate to Administration - Server Management screen, then the Components view.
2. In the Components list, select the unavailable server component of interest.

Note: Make sure that you select the server component on the Siebel Server of interest.

3. Click Shutdown.

After the server component shuts down, its state changes to Shutdown.

4. After the server component shuts down, click Startup.

When the server component starts, its state changes to Starting Up. After the server component has started, the state changes to Running.

Pausing Server Components on a Siebel Server

This topic describes how to pause a server component on a Siebel Server.

This topic is part of "[Administering Siebel Server Components](#)" on page 6-3.

To pause a server component on a Siebel Server

1. Navigate to Administration - Server Management screen, then the Components view.
2. In the Components list, select the server component of interest.

Note: Make sure that you select the server component on the Siebel Server of interest.

3. Click Pause.

Resuming Server Components on a Siebel Server

This topic describes how to resume a server component on a Siebel Server that you previously paused.

This topic is part of "[Administering Siebel Server Components](#)" on page 6-3.

To resume a server component on a Siebel Server

1. Navigate to Administration - Server Management screen, then the Components view.
2. In the Components list, select the server component of interest.

Note: Make sure that you select the server component on the Siebel Server of interest.

3. Click Resume.

Administering Component Jobs

This topic lists the administration tasks applicable to component jobs.

This topic includes the following information:

- "[About Component Jobs](#)" on page 6-6
- "[Starting a Component Job](#)" on page 6-6
- "[Starting a Repeating Component Job](#)" on page 6-8
- "[Deleting a Component Job or Repeating Component Job](#)" on page 6-9
- "[Canceling a Component Job or Repeating Component Job](#)" on page 6-9
- "[Holding a Component Job or Repeating Component Job](#)" on page 6-10

- ["Resuming a Component Job or Repeating Component Job"](#) on page 6-10
- ["Troubleshooting Component Jobs"](#) on page 6-10

About Component Jobs

A component job is a request for one or more Siebel Server tasks to run. A component job is initiated by either the user or the system, and the Siebel Server runs one or more tasks to fulfill the component job. Component jobs can:

- Be scheduled
- Be repeated
- Use component job templates

Make sure that your Siebel Enterprise and Siebel Server configurations allow tasks to run for a server component.

If you are planning to regularly run component jobs with the same parameter values, then configure a component job template, which is a predefined component job.

Only batch-mode component tasks are started by running a component job. Background-mode components, such as Workflow Monitor Agent (alias WorkMon), are started by the Siebel Server when the component is started. The parameter Default Tasks (alias DfltTasks) defines the number of tasks started for the background-mode component. Background-mode component tasks can also be started by using the Server Manager command-line interface program.

This topic is part of ["Administering Component Jobs"](#) on page 6-5.

Related Topics

["Checking Your Siebel Enterprise and Siebel Server Configurations"](#) on page 4-22

["Configuring Component Job Templates"](#) on page 4-16

[Chapter 7, "Using the Siebel Server Manager Command-Line Interface"](#)

["Troubleshooting Component Jobs"](#) on page 6-10

Starting a Component Job

This topic describes how to create and start an individual component job. You can run a component job by using either server components or component job templates. An individual component job is scheduled to run once at a specific time.

This topic is part of ["Administering Component Jobs"](#) on page 6-5.

To start a component job

1. Navigate to Administration - Server Management screen, then the Jobs view.
2. In the Jobs list, click New.

The component job status field changes to Creating.

3. In the Component/Job field, click the drop-down list.

Note: If the Component/Job drop-down list contains no records, then synchronize the Siebel Server components.

4. In the Component/Job drop-down list, select a server component or component job and click OK.

If you want to use a component job template for your component job, then you must first define the component job template.

5. In the Job Detail view, enter data in other appropriate fields as described in the following table. Click Menu, and then Save Record.

Field	Description
Scheduled Start	The scheduled start date and time of the component job.
Expiration	The date at which the component job is no longer valid.
Requested Server	Set if you want to target a server component on a specific Siebel Server.
Request Key	Set if you want to target a component or repeating component job to a specific instance of the server component identified by the request key. In all other situations, keep this field blank.
Delete Interval	Set with Delete Unit field, this field determines the length of time before the component job is deleted. If it is not updated, then this field defaults to 1.
Delete Unit	Set with Delete Interval field, this field determines the length of time before the component job is deleted. If it is not updated, then this field defaults to Weeks.
Retry on Error	Check this box to retry the component job in case of error.
Sleep Time	This field is available when the Retry on Error check box is True and determines the amount of time before the component job is retried.
Number of Retries	This field is available when the Retry on Error check box is True and determines the number of times the component job is retried.

6. In the Job Parameters list, add or change any component job parameters for the component job:

- a. Click New.
- b. In the Name field, click the select button.

The Job Parameters dialog box appears. The parameters that appear in the Job Parameters dialog box vary depending on the server component that you specified in Step 3.

- c. Select a parameter in the Component Parameters dialog box, and modify its value.
- d. Click Menu, and then Save Record.

7. In the Jobs list, click Submit Job.

The Status field changes from Creating to Queued.

Related Topics

["About Component Jobs"](#) on page 6-6

["Configuring Component Job Templates"](#) on page 4-16

["Starting a Repeating Component Job"](#) on page 6-8

["Synchronizing Components on a Siebel Enterprise Server"](#) on page 4-17

Starting a Repeating Component Job

This topic describes how to create and start a repeating component job. You can define repeating component jobs by using either components or component job templates, and you can schedule component jobs to run repeatedly at specific times over specific intervals. In order to run repeating component jobs, both the Server Request Broker (alias SRBroker) and Server Request Processor (alias SRProc) server components must be running. If you have to run repeating jobs at unspecified times or intervals, then run repeating component jobs by using a component job template.

Note: It is not possible to start a business service directly as a repeating component job. To accomplish this task, you first must include the business service in a workflow process. You can then run the workflow process as a repeating component job for the Workflow Process Batch Manager component (alias WfProcBatchMgr).

This topic is part of "[Administering Component Jobs](#)" on page 6-5.

To start a repeating component job

1. Create a component job as described in "[Starting a Component Job](#)" on page 6-6, but do not start the component job.
2. In the Job Detail view, enter data in the Repeating Info fields as described in the following table. Click Menu, and then Save Record.

Field	Description
Repeating?	Select this check box to make the component job a repeating component job.
Repeat Unit	This field determines the length of time before the component job repeats when it is set with the Repeat Interval field.
Repeat Interval	Set with Repeat Unit field, this field determines the length of time before the component job repeats.
Repeat From	This field has three possible settings: <ul style="list-style-type: none"> ■ Scheduled Start. Starts the next iteration of the repeating component job after the interval period has elapsed. The interval period is calculated from the time indicated by the Scheduled Start field. For example, if the repeat interval is 5 minutes, the scheduled start time is 09:00, and the component job starts at 09:02, then the next component job is scheduled to start at 09:05. Using this setting might result in a backlog of component jobs that will be started if the actual start time is later than the scheduled start time. ■ Actual Start. Starts the next iteration of the repeating component job after the interval period has elapsed. The interval period is calculated from the time the component job starts rather than the time indicated by the Scheduled Start field. For example, if the repeat interval is 5 minutes, the scheduled start time is 09:00, and the component job starts at 09:02, then the next component job is scheduled to start at 09:07. ■ End. Starts the next iteration of the repeating component job after the previous component job ends and the repeat interval has elapsed. For example, if the repeat interval is 5 minutes, the scheduled start time is 09:00, the component job starts at 09:02, and the first component job ends at 09:04, then the next component job is scheduled to start at 09:09.
Repetitions	This field determines the number of times the component job repeats.

3. In the Jobs list, click Submit Job.

The Status field changes from Creating to Active.

Related Topics

["Configuring Component Job Templates"](#) on page 4-16

["About Component Jobs"](#) on page 6-6

["Starting a Component Job"](#) on page 6-6

Deleting a Component Job or Repeating Component Job

This topic describes how to delete a component job. You can only delete component jobs that have a status of Creating. After the component job has been submitted, you can only cancel the component job.

Note: You can also delete component jobs by setting the Delete Interval and Delete Units field while creating the component job. After the component job has been started, these fields are read-only.

This topic is part of ["Administering Component Jobs"](#) on page 6-5.

To delete a component job or repeating component job during its creation

1. Navigate to Administration - Server Management screen, then the Jobs view.
2. In the Jobs list, select the component job that has a Status field value of Creating.
3. Click Delete.

Completed component jobs are deleted automatically after a configurable period of time. The fields Delete Interval and Delete Units determine this period and are set, by default, to one week.

Related Topics

["Starting a Component Job"](#) on page 6-6

["Administering Component Jobs"](#) on page 6-5

["Canceling a Component Job or Repeating Component Job"](#) on page 6-9

Canceling a Component Job or Repeating Component Job

This topic describes how to cancel component jobs. You can only cancel component jobs that have a state of Queued or On-Hold.

This topic is part of ["Administering Component Jobs"](#) on page 6-5.

To cancel a component job or repeating component job

1. Navigate to Administration - Server Management screen, then the Jobs view.
2. In the Jobs list, select the component job that has a Status field value of Queued or On-Hold.
3. Click Cancel Job.

Canceled component jobs are deleted automatically after a configurable period of time. The fields Delete Interval and Delete Units determine this period and are set, by default, to one week.

Related Topics

["Starting a Component Job"](#) on page 6-6

Holding a Component Job or Repeating Component Job

This topic describes how to hold component jobs. You can only hold component jobs that have a state of Queued.

Holding a component job pauses the applicable task (if the task can be paused) or allows the current task to finish. No new tasks begin for the held component job.

This topic is part of "[Administering Component Jobs](#)" on page 6-5.

To hold a component job or repeating component job

1. Navigate to Administration - Server Management screen, then the Jobs view.
2. In the Jobs list, select the component job that has a Status field value of Queued.

Note: You cannot hold jobs with an Active value in the Status field.

3. Click Hold Job.

Resuming a Component Job or Repeating Component Job

This topic describes how to resume component jobs put on hold. You can only resume component jobs that have a state of On Hold.

This topic is part of "[Administering Component Jobs](#)" on page 6-5.

To resume a component job or repeating component job on hold

1. Navigate to Administration - Server Management screen, then the Jobs view.
2. In the Jobs list, select the component job that has a Status field value of On Hold.
3. Click Resume Job.

Related Topics

["Holding a Component Job or Repeating Component Job"](#) on page 6-10

Troubleshooting Component Jobs

This topic provides guidelines for resolving problems with component jobs.

This topic is part of "[Administering Component Jobs](#)" on page 6-5.

To resolve the problem, look for it in the list of symptoms or error messages in [Table 6-1](#).

Table 6–1 Resolving Component Job Problems

Problem	Cause	Solution
The Component/Jobs drop-down list contains no records.	Batch-mode components are not synchronized.	Synchronize the batch-mode components.
	Server component job is based on a new component definition that was added by using the component definition view.	Synchronize the batch-mode components.

Related Topics

["Synchronizing Components on a Siebel Enterprise Server"](#) on page 4-17

Administering Siebel Server Tasks

This topic lists the administration tasks applicable to Siebel Server tasks. It contains the following information:

- ["Starting a Siebel Server Task"](#) on page 6-11
- ["Pausing a Siebel Server Task"](#) on page 6-11
- ["Resuming a Siebel Server Task"](#) on page 6-12
- ["Stopping a Siebel Server Task"](#) on page 6-12
- ["Terminating a Siebel Server Task"](#) on page 6-13
- ["Configuring Siebel Server Task Dynamic Parameters"](#) on page 6-13

Starting a Siebel Server Task

To start a Siebel Server task, you must run a component job. For information about component jobs and administering component jobs, see the following topics:

- ["About Component Jobs"](#) on page 6-6
- ["Administering Component Jobs"](#) on page 6-5
- ["Starting a Component Job"](#) on page 6-6

This topic is part of ["Administering Siebel Server Tasks"](#) on page 6-11.

Pausing a Siebel Server Task

This topic describes how to pause a Siebel Server task. You can pause Siebel Server tasks only for certain component types. [Table 6–2](#) lists the component types and the predefined components that have this feature.

Table 6–2 Pausable Component Types

Component Types	Predefined Component	Predefined Component Alias
MailMgr	Email Manager	MailMgr
MktgSrvr	Marketing Server	MktgSrvr
PageMgr	Page Manager	PageMgr
ServerMgr	Server Manager	ServerMgr

Table 6–2 (Cont.) Pausable Component Types

Component Types	Predefined Component	Predefined Component Alias
TxnMerge	Transaction Merger	TxnMerge
TxnProc	Transaction Processor	TxnProc
TxnRoute	Transaction Router	TxnRoute
WorkActn	Workflow Action Agent	WorkActn
WorkMon	Workflow Monitor Agent	WorkMon

This topic is part of "[Administering Siebel Server Tasks](#)" on page 6-11.

To pause a Siebel Server task

1. Navigate to Administration - Server Management screen, then the Tasks view.
2. In the Tasks list, select the Siebel Server task of interest.

Make sure that the Siebel Server task is on the Siebel Server of interest and is of a component type that can be paused. See [Table 6–2](#) for a list of Siebel Server component types that can be paused.

3. Click Pause.

Related Topics

["Administering Siebel Server Tasks"](#) on page 6-11

["Resuming a Siebel Server Task"](#) on page 6-12

Resuming a Siebel Server Task

This topic describes how to resume a paused Siebel Server task.

This topic is part of "[Administering Siebel Server Tasks](#)" on page 6-11.

To resume a paused Siebel Server task

1. Navigate to Administration - Server Management screen, then the Tasks view.
2. In the Tasks list, select the paused Siebel Server task of interest.
3. Click Resume.

Related Topics

["Administering Siebel Server Tasks"](#) on page 6-11

["Pausing a Siebel Server Task"](#) on page 6-11

Stopping a Siebel Server Task

This topic describes how to stop a Siebel Server task. You can stop running or paused Siebel Server tasks.

Note: It is preferable to stop the individual tasks for a given server component rather than shutting down the server component.

This topic is part of "[Administering Siebel Server Tasks](#)" on page 6-11.

To stop a Siebel Server task

1. Navigate to Administration - Server Management screen, then the Tasks view.
2. In the Tasks list, select the running Siebel Server task of interest.
3. Click Stop.

Related Topics

["Administering Siebel Server Tasks"](#) on page 6-11

Terminating a Siebel Server Task

This topic describes how to terminate a Siebel Server task. Terminating a Siebel Server task signals the Siebel Server to use the operating system control to terminate the task.

This topic is part of ["Administering Siebel Server Tasks"](#) on page 6-11.

To terminate a Siebel Server task

1. Navigate to Administration - Server Management screen, then the Tasks view.
2. In the Tasks list, select the running Siebel Server task of interest.
3. Click Stop three times in succession.

Related Topics

["Administering Siebel Server Tasks"](#) on page 6-11

Configuring Siebel Server Task Dynamic Parameters

This topic describes how to configure dynamic parameters of a Siebel Server task. Siebel Server task parameters consist of Siebel Enterprise Server, Siebel Server, and server component-level parameters, as well as task-specific parameters specified when starting a component job. After a task is running, only dynamic parameters can be changed.

This topic is part of ["Administering Siebel Server Tasks"](#) on page 6-11.

To configure Siebel Server task dynamic parameters

1. Navigate to Administration - Server Management screen, then the Tasks view.
2. In the Tasks list, select the running Siebel Server task of interest.
3. Click the Parameters tab.
4. In the Task Parameters list, change the values of the parameters that you want to modify. (Identify dynamic parameters by a check in the Effective Immediately column.)
 - a. Select the parameter that you want to modify.
 - b. In the Value field, type in the new value.
 - c. Click Menu, and then Save Record.

Related Topics

["About Siebel System Parameters"](#) on page 4-2

["About Task Parameters"](#) on page 4-6

["Administering Siebel Server Tasks"](#) on page 6-11

["Siebel Enterprise, Server, and Component Parameters"](#) on page A-11

Using the Siebel Server Manager Command-Line Interface

This chapter describes how to use the Siebel Server Manager command-line interface. It includes the following topics:

- [Starting the Siebel Server Manager Command-Line Interface](#)
- [Recommendations for Using the Command-Line Interface](#)
- [Siebel Server Manager Commands](#)

Starting the Siebel Server Manager Command-Line Interface

The topics in this chapter describe the procedures available from the Siebel Server Manager command-line interface, which is also known as the `svrmgr` program. This program is available on both the Windows and UNIX environments.

An overview of the `svrmgr` program and its administration is followed by individual commands used to administer the Siebel Enterprise Server, individual Siebel Servers, and Siebel Server components and component groups. You must have administrative responsibilities defined by the Siebel application and have a user definition in the database in order to access and use the Siebel Server Manager command-line interface.

Note: When using the Siebel Server Manager command-line interface, only use ASCII characters. If you want to enter parameters containing non-ASCII characters (for example, accented French characters, or Russian, Arabic, Japanese, Chinese, Korean, or Thai characters), then use the Siebel Server Manager GUI.

Starting the Siebel Server Manager Program

This procedure describes how to start the Siebel Server Manager program, `svrmgr`.

To start the `svrmgr` program

1. For Windows servers only: at the DOS prompt, change to the `bin` subdirectory within the Siebel Server root directory:

```
cd SIEBSRVR_ROOT\bin
```

Note: You cannot use the Uniform Naming Convention (UNC) in the Siebel Server Manager command when specifying the path and computer names.

- Execute the `srvrmgr` program using flags to specify the parameters that you want:

```
srvrmgr flags
```

For a list of `srvrmgr` flags, see [Table 7-2](#).

- After the Siebel Server Manager has started, the prompt changes to:

```
srvrmgr:server_name>
```

The `server_name` parameter appears in the prompt only if you executed the `srvrmgr` program by specifying a Siebel Server using the `/s` or `-s` flag, or after you specify a Siebel Server by using the `set server` command.

For example, to start the `srvrmgr` program using the parameters specified in [Table 7-1](#) on a Windows server, enter a command like the following:

```
srvrmgr /g gateway1:2320 /e enterprise1 /s server1 /u sadmin /p pwd
```

To start the `srvrmgr` program using the parameters specified in [Table 7-1](#) on a UNIX server, enter a command like the following:

```
srvrmgr -g gateway1:2320 -e enterprise1 -s server1 -u sadmin -p pwd
```

Table 7-1 Example Parameters for Starting the `srvrmgr` Program

Siebel Gateway	Enterprise	Siebel Server	User Name	Password
gateway1	enterprise1	server1	sadmin	pwd

Command-Line Flags for the Siebel Server Manager Program

[Table 7-2](#) lists the command-line flags available for the Siebel Server Manager program, `srvrmgr`.

Table 7-2 Command-Line Flags for `srvrmgr`

Windows Flag	UNIX Flag	Parameter	Description	Required
<code>/b</code>	<code>-b</code>	Not applicable	Batch mode (use with <code>/i</code> to indicate exit when an error is encountered).	No
<code>/c</code>	<code>-c</code>	<code>"command"</code>	Executes a single command (the command must be bounded within double quotes).	No
<code>/e</code>	<code>-e</code>	<code>entrpr_server</code>	Siebel Enterprise Server name.	Yes
<code>/g</code>	<code>-g</code>	<code>gateway_server</code>	Network address of the Siebel Gateway. This value is usually provided with the TLS port for the Siebel Gateway, as specified during installation. For example, the value provided using this flag might be <code>gateway1:2320</code> .	Yes
<code>/h</code> or <code>/?</code>	<code>-h</code> or <code>-?</code>	Not applicable	Prints a usage help message	No
<code>/i</code>	<code>-i</code>	<code>input_file</code>	Gets commands from the input file	No

Table 7–2 (Cont.) Command-Line Flags for *srvrmgr*

Windows Flag	UNIX Flag	Parameter	Description	Required
/k	-k	<i>delimiter</i>	Uses delimiter specified to parse columns in output file	No
/l	-l	<i>language</i>	Language code (default is ENU)	No
/m	-m	Not applicable	Compression enabled	No
/o	-o	<i>output_file</i>	Logs information generated in interactive mode to the specified output file. The types of information logged include, for example, the command issued, command output, type of task, task status, start time, and end time. Use this flag with either the flag that specifies a command to log (c) or the flag that specifies an input file with numerous commands (i).	No
/p	-p	<i>password</i>	Siebel Server administrator password	Yes
/r	-r	Not applicable	Encryption for network packets is enabled (default is N)	No
/s	-s	<i>siebel_server</i>	Siebel Server name (the default is all servers). Starting <i>srvrmgr</i> with this flag connects the program only with that specific Siebel Server. All commands and user authentication are sent only to that Siebel Server. You cannot change the targeted Siebel Server in this mode.	No
/u	-u	<i>username</i>	Siebel Server administrator user name Note: The <i>srvrmgr</i> program expects the database to store user names in upper-case format. User names are automatically converted to upper case during the authentication process and login issues result if database user names are stored in lower case.	Yes
/z	-z	<i>server_group_name</i>	Server group name. Starting <i>srvrmgr</i> with this flag connects the program to the specified server group and, as a result, to all of the Siebel Servers that are assigned to the server group. For information about managing the assignment of Siebel Servers with server groups, see " Server Group Management Commands " on page 7-12.	No

About Error Handling for the Siebel Server Manager Program

Error codes are returned by the Siebel Server Manager program (*srvrmgr*) in the manner described in this topic. Program behavior is described for different usage cases, including those based on the flags that you use to run *srvrmgr*. Any nonzero

values returned are those that might be expected from a shell script. In earlier versions of Siebel CRM, `srvrmgr` returns 0 (zero) in all of the following cases.

- When you run `srvrmgr` with valid syntax and valid arguments for flags and no error occurs, then `srvrmgr` returns 0 (zero).
- When you run `srvrmgr` with invalid syntax, such as without the required flag `/g` or `-g`, then `srvrmgr` returns a nonzero value.
- When you run `srvrmgr` with valid syntax but with invalid arguments for any flags, such as with an invalid user name with the `/u` or `-u` flag, then `srvrmgr` returns a nonzero value.
- When you run `srvrmgr` with the `/c` or `-c` flag:
 - If no error occurs, then `srvrmgr` returns 0 (zero).
 - If any error occurs, then `srvrmgr` returns a nonzero value.
- When you run `srvrmgr` with the `/i` or `-i` flag and without the `/b` or `-b` flag:
 - If no error occurs, then `srvrmgr` returns 0 (zero).
 - If one or more command process specified in the input file fails, then `srvrmgr` returns 0 (zero).
 - If `srvrmgr` cannot connect with the Siebel Gateway or cannot open the specified input or output file, then `srvrmgr` returns a nonzero value.
- When you run `srvrmgr` with the `/i` or `-i` flag and the `/b` or `-b` flag:
 - If no error occurs, then `srvrmgr` returns 0 (zero).
 - If any error occurs, then `srvrmgr` returns a nonzero value.

Recommendations for Using the Command-Line Interface

This topic provides recommendations for using the Server Manager command-line interface.

- Target specific Siebel Servers without using the `/s` or `-s` flag:
 - Use the directive for `server siebel_server_name` in individual commands. Specifying the name of a specific Siebel Server targets the command to only that Siebel Server.
 - Use a partial name with the `%` wildcard character to target the command to all of the Siebel Servers with names matching the pattern. Only patterns that start or end with the wildcard character are matched. Wildcards in the middle of the string are not matched. For example, the following command lists components for all of the Siebel Servers with a name beginning with WF:


```
list components for server WF%
```
 - Use the command `set server siebel_server_name`. To return to the mode where commands are targeted to all of the Siebel Servers, use `unset server`. For more information about these commands, see "[Siebel Server Manager Environment Commands](#)" on page 7-7.

Note: When you are using the `set` command, the connections to other Siebel Servers are maintained and continue to run.

- Start `srvrmgr` using the `/s` or `-s` flag for frequent list operations. Parse the resulting data for each Siebel Server. Aggregate the list data for the enterprise externally to the `srvrmgr` process. This method improves performance by keeping `srvrmgr` from serializing the operations.
- Use the `show` clause to specify only the columns with data that you are using. For more information about using the `show` clause, see ["List Command Configuration"](#) on page 7-12.
- Use the `/i` or `-i` option to open a single long-running `srvrmgr` session and send it commands rather than using the `/c` or `-c` option. You can also execute commands conditionally from a script, by using the `/i` or `-i` option.
- When using `srvrmgr` commands from a file or script, use the `sleep` command to configure wait periods (in seconds) before the next `srvrmgr` command. For example, after starting the Siebel Server, use the `sleep` command to wait until the Siebel Server and its component are running before issuing the next command.
- Use the `read` command during an active `srvrmgr` session to dynamically input `srvrmgr` commands from a file.
- Specify a value for the parameter `TaskTag` when starting a new task. This text appears in the `list tasks` command if you include the `TK_TASKTAG` column. For example, enter a command like the following:

```
list tasks show TK_TASKTAG
```

- Start `srvrmgr` using the `/z` or `-z` flag to connect to a server group. For example, on a Windows server, enter a command like the following:

```
srvrmgr /g gateway1 /e enterprise1 /z server_group_name /u sadmin /p pwd
```

On a UNIX server, enter a command like the following:

```
srvrmgr -g gateway1 -e enterprise1 -z server_group_name -u sadmin -p pwd
```

This command connects you to all of the Siebel Servers assigned to the server group.

Siebel Server Manager Commands

After the Siebel Server Manager has been started, you can execute administrative tasks by using the commands described in this topic.

These commands can also be written into an ASCII text file, exactly as you execute them through the Siebel Server Manager, and used as a batch input file by running `srvrmgr` by using the `/i` or `-i` flag. Running the batch input file is especially useful in the administration of similar Siebel Server component definitions for multiple Siebel Servers.

Note: You must have the Siebel Administrator responsibility to connect with the `srvrmgr` command-line tool.

The Siebel Server Manager commands are divided into the following categories:

- **Help.** For more information, see ["Help Commands"](#) on page 7-7.
- **Environment.** For more information, see ["Siebel Server Manager Environment Commands"](#) on page 7-7.

- **List.** For more information, see "[List Commands](#)" on page 7-8 and "[List Command Configuration](#)" on page 7-12.
- **Siebel Server management.** For more information, see "[Siebel Server Management Commands](#)" on page 7-13.
- **Component group definition.** For more information, see "[Component Group Definition Commands](#)" on page 7-13.
- **Component definition.** For more information, see "[Component Definition Commands](#)" on page 7-15 and "[Reconfiguring Component Definition Commands](#)" on page 7-16.
- **Component management.** For more information, see "[Component Management Commands](#)" on page 7-17.
- **Task management.** For more information, see "[Task Management Commands](#)" on page 7-18.
- **Parameter management.** For more information, see "[Parameter Management Commands](#)" on page 7-20.
- **Named subsystem management.** For more information, see "[Named Subsystem Management Commands](#)" on page 7-21.
- **System alert notification.** For more information, see "[System Alert Notification Commands](#)" on page 7-22.
- **List definition.** For more information, see "[List Definition Commands](#)" on page 7-22 and "[List Parameter Override Commands](#)" on page 7-22.
- **Event logging.** For more information, see "[Event Logging Commands](#)" on page 7-23.
- **Preferences.** For more information, see "[Server Manager Command-Line Preferences](#)" on page 7-24.

Command Syntax

This topic lists the command-line syntax and usage for Siebel Server Manager commands.

Component names and parameter names used in the command-line interface differ from the Siebel Server Manager GUI. To get the actual component and parameter names used in the command-line interface, use the list commands. For information about using the list commands, see "[List Commands](#)" on page 7-8.

For user-defined values such as *siebel_server_name*, *component_alias_name*, and *parameter_alias_name*, you must enclose these values in quotes if the value:

- Contains spaces
- Is a keyword such as `server` or `component` that you do not want to be parsed

For example, you must enclose the Siebel Server name in double quotes for the following command, because the Siebel Server name contains a space:

```
start task for component EIM server "North America" with Config=default.ifb
```

Note: If a `svrmgr` command contains nested quotes, that is, quotes contained within quotes, then precede the inner quotes by the backslash escape character (`\`).

Help Commands

Use the Help command to retrieve a list of commands or obtain help on a specific command.

To obtain help

- Enter the following command:

```
help
```

- For a specific command, enter a command like the following:

```
help command
```

Siebel Server Manager Environment Commands

Use environment commands to set the Siebel Server Manager environment variables, which control the current Siebel Server Manager session.

To set the current working Siebel Server

- Enter the following command:

```
set server siebel_server_name
```

This command works only if you did not specify a Siebel Server when executing the `svrmgr` program using the `-s` flag.

To unset (clear) the current working Siebel Server

- Enter the following command:

```
unset server
```

This command works only if you did not specify a Siebel Server when executing the `svrmgr` program using the `-s` flag.

To show the environment variables

- Enter the following command:

```
show
```

To show an individual environment variable

- Enter the following command:

```
show variable_name
```

To spool output to a file

- Enter the following command:

```
spool output_file
```

To stop spooling to a file

- Enter the following command:

```
spool off
```

To read commands from a file

- Enter the following command:

```
read input_file
```

To refresh the Siebel Enterprise Server connections

- Enter the following command:

```
refresh enterprise
```

The `refresh enterprise` command closes all of the connections to the existing Siebel Servers and creates new connections to these servers.

To remove header and footer information from `srvrmgr` command-line output

- Enter the following command:

```
set header false
```

and

```
set footer false
```

Removing the header and footer information is useful if you are trying to parse the output of `srvrmgr` commands.

To add header and footer information to the `srvrmgr` command-line output

- Enter the following command:

```
set header true
```

and

```
set footer true
```

To exit the `srvrmgr` program

- Enter the following command:

```
exit
```

or

```
quit
```

To save any configuration changes prior to exiting, use a `backup` command listed in "[Siebel Server Management Commands](#)" on page 7-13.

List Commands

Use the `list` command to display current data only. This command does not change any data.

To list available Siebel Servers

- Enter the following command:

```
list servers
```

- For a component, enter the following command:

```
list servers for component component_alias_name
```

- For a component group, enter the following command:

```
list servers for component group component_group_alias_name
```

To list component groups

- For all component groups, enter the following command:

```
list component groups
```

- For a particular Siebel Server, enter the following command:

```
list component groups for server siebel_server_name
```

If you are connected to the Siebel Server, then the `list` commands list only component groups from shared memory. Otherwise, it lists the component groups assigned to that Siebel Server from the Siebel Gateway. See also the `describe` command in "[Component Group Definition Commands](#)" on page 7-13.

To list current component group status

- For all instances of the component group, enter the following command:

```
list component group component_group_alias_name
```

- For a particular Siebel Server, enter the following command:

```
list component group component_group_alias_name for server siebel_server_name
```

To list current component status

- For all components, enter the following command:

```
list component
```

- For all instances of the component, enter the following command:

```
list component component_alias_name
```

- For a particular Siebel Server, enter the following command:

```
list component for server siebel_server_name
```

- For a particular task, enter the following command:

```
list component for task task_number
```

To list values for a particular task, you first must set the current working Siebel Server by using the `set server` command. For information about this command, see "[Siebel Server Manager Environment Commands](#)" on page 7-7.

To list subsystems

- For all subsystems, enter the following command:

```
list subsystem
```

To list named subsystems

- For all named subsystems, enter the following command:

```
list named subsystem
```

- For a particular subsystem, enter the following command:

```
list named subsystem for subsystem subsystem_alias_name
```

- For a particular Siebel Server, enter the following command:

```
list named subsystem for server siebel_server_name
```

To list current processes

- Enter the following command:

```
list processes
```

To list the status of current tasks

- For all tasks, enter the following command:

```
list tasks
```

- For a particular Siebel Server, enter the following command:

```
list tasks for server siebel_server_name
```

- For a particular component, enter the following command:

```
list tasks for component component_alias_name
```

- For a particular component group, enter the following command:

```
list tasks for component group component_group_alias_name
```

- For a particular task, enter the following command:

```
list task task_number
```

To list values for a particular task, you first must set the current working Siebel Server by using the `set server` command. For information about this command, see ["Siebel Server Manager Environment Commands"](#) on page 7-7.

Note: The number of tasks returned is determined by the Maximum Tasks parameter for that component. For more information about the Maximum Tasks parameter, see ["Siebel Enterprise, Server, and Component Parameters"](#) on page A-11.

To list tasks for session mode components

- For a particular Siebel Server, enter the following command:

```
list sessions for server siebel_server_name
```

- For a particular component, enter the following command:

```
list sessions for comp component_alias_name
```

- For a particular Application Object Manager login, enter the following command:

```
list sessions for login object_manager_login
```

- For a list of hung tasks, enter the following command:

```
list hung sessions for server siebel_server_name [or] comp component_alias_name [or] login object_manager_login
```

- For a list of active tasks, enter the following command:

```
list active sessions for server siebel_server_name [or] comp component_alias_name [or] login object_manager_login
```

To list current parameter values

- For the Siebel Enterprise Server, enter the following command:

```
list ent param
```

- For all Siebel Servers, enter the following command:
`list parameters`
- For a particular Siebel Server, enter the following command:
`list parameters for server siebel_server_name`
- For a particular component on all Siebel Servers, enter the following command:
`list parameters for component component_alias_name`
- For a particular component on a particular Siebel Server, enter the following command:
`list parameters for component component_alias_name server siebel_server_name`
- For a particular task, enter the following command:
`list parameters for task task_number server siebel_server_name`

To list current advanced parameter values

- Use the previously documented commands for listing parameters, but preface advanced `before` parameters. For example:
`list advanced parameters for server siebel_server_name`

To list current state values

- For all state values, enter the following command:
`list state values`
- For a particular Siebel Server, enter the following command:
`list state values for server siebel_server_name`
- For a particular task, enter the following command:
`list state values for task task_number`

To list values for a particular task, you first must set the current working Siebel Server by using the `set server` command. For information about this command, see "[Siebel Server Manager Environment Commands](#)" on page 7-7.

To list current statistic values

- For all statistics, enter
`list statistics`
- For a particular Siebel Server, enter the following command:
`list statistics for server siebel_server_name`
- For a particular component, enter the following command:
`list statistics for component component_alias_name`
- For a particular task, enter the following command:
`list statistics for task task_number`

To list values for a particular task, you first must set the current working Siebel Server by using the `set server` command. For information about this command, see "[Siebel Server Manager Environment Commands](#)" on page 7-7.

List Command Configuration

The following commands modify or configure the output for the list commands described in "[List Commands](#)" on page 7-8.

To modify the output of an individual list command

- To display specific columns, enter the following command:

```
list list_object
  show column_1, column_2, ..., column_n
```

For example:

```
list components show SV_NAME, CC_ALIAS
```

- To display specific columns with a `for` clause, enter the following command:

```
list list_object
  for for_object
  show column_1, column_2, ..., column_n
```

For example:

```
list components for SRVR_1 show CC_ALIAS
```

To list available columns for a list command

- Enter the following command:

```
configure list list_object
```

To configure the output of the list command

- To display only specific columns, enter the following command:

```
configure list list_object
  show column_1, column_2, ..., column_n
```

This command changes future `list list_object` commands to display only those columns defined.

Note: Once you configure a specific list command for a given `svrmgr` session, it cannot be configured again in that session. A new session must be started to view other columns for that list command.

Server Group Management Commands

Use the server group management commands to manage the assignment of Siebel Servers with server groups. A Siebel Server can only be assigned to one server group at a time. A server group can contain many Siebel Servers.

Once you assign Siebel Servers to a server group, you can specify the server group name as a parameter for the `/z` or `-z` flag when starting the `svrmgr` program. Specifying the server group connects the `svrmgr` program to all of the Siebel Servers assigned to the specified server group.

For example, on a Windows server, enter a command like the following:


```
srvrmgr /g gateway1 /e enterprise1 /z server_group_name /u sadmin /p pwd
```

On a UNIX server, enter a command like the following:

```
srvrmgr -g gateway1 -e enterprise1 -z server_group_name -u sadmin -p pwd
```

For more information about starting the `srvrmgr` program, see ["Starting the Siebel Server Manager Command-Line Interface"](#) on page 7-1.

To assign a Siebel Server to a server group

- Enter the following command:

```
change attribute groupname=server_group_name for server siebel_server_name
```

To unassign a Siebel Server from a server group

- Enter the following command:

```
change attribute groupname=" " for server siebel_server_name
```

Note: Make sure to include a space between the quotation marks.

Siebel Server Management Commands

Use the Siebel Server management commands to start or stop a Siebel Server.

To start a Siebel Server

- Enter the following command:

```
startup appserver siebel_server_name
```

To shut down a Siebel Server

- Enter the following command:

```
shutdown appserver siebel_server_name
```

You can also back up the Siebel Gateway registry, as described in the steps that follow.

To back up the Siebel Gateway registry

1. For the installed Siebel Gateway, navigate to the directory `GTWYSRVR_ROOT\zookeeper\conf`.
2. Verify the `dataDir` path from the `zoo1.cfg` file.
3. Within this path, navigate to the `version-2` directory.
4. Copy the `version-2` directory to another location.

Component Group Definition Commands

Use these commands to create, delete, assign, remove, enable, and disable component groups.

To create a component group

- Enter the following command:

```
create component group component_group_alias_name full name "descriptive_name"
description "description_of_component_group"
```

To assign a component group to a Siebel Server

- Enter the following command:

```
assign component group component_group_alias_name to server siebel_server_name
```

To unassign a component group from a Siebel Server

- Enter the following command:

```
unassign component group component_group_alias_name from server siebel_server_name
```

Note: Unassigning a component group from a Siebel Server results in a loss of component group customization, for example, parameter settings. Before unassigning a component group, review "[About Assigned and Unassigned Component Groups](#)" on page 4-8.

To enable a component group for the Siebel Enterprise Server

1. Enter the following command:

```
enable component group component_group_alias_name
```

2. Stop and restart the system service to make the changes take effect.

For more information about how to stop or start the Siebel Server system service, see "[Administering the Siebel Server System Service](#)" on page 5-7.

This procedure works only if you did not run Siebel Server Manager command-line interface using the /s or -s flag.

Note: Before you enable a component group for the Siebel Enterprise Server, at least one component in the group must be active.

To enable a component group on a Siebel Server

1. Enter the following command:

```
enable component group component_group_alias_name to server siebel_server_name
```

2. Stop and restart the system service to make the changes take effect.

For more information about how to stop or start the Siebel Server system service, see "[Administering the Siebel Server System Service](#)" on page 5-7.

Note: Use this command when enabling a component that was previously disabled on a particular server. Newly created component groups are enabled by default.

To disable a component group for the Siebel Enterprise Server

1. Enter the following command:

```
disable component group component_group_alias_name
```

2. Stop and restart the system service to make the changes take effect.

For more information about how to stop or start the Siebel Server system service, see "[Administering the Siebel Server System Service](#)" on page 5-7.

To disable a component group for a Siebel Server

1. Enter the following command:

```
disable component group component_group_alias_name for server siebel_server_name
```

2. Stop and restart the system service to make the changes take effect.

For more information about how to stop or start the Siebel Server system service, see ["Administering the Siebel Server System Service"](#) on page 5-7.

To list component groups from the Siebel Gateway

- Enter the following command:

```
describe component group
```

The describe command lists the component groups from the Siebel Gateway.

To remove a component group from a Siebel Server

- Enter the following command:

```
remove component group component_group_alias_name from server siebel_server_name
```

To delete a component group

- Enter the following command:

```
delete component group component_group_alias_name
```

In order for you to delete a component group, the component group cannot contain any server components or component definitions.

Component Definition Commands

Use the component definition commands to create, activate, or delete defined components. Component definitions are contained in component groups, both of which are defined at the Siebel Enterprise Server level. To use a new component, make sure that the component definition is activated and the component group containing the new component is assigned to the appropriate server. For component group commands, see ["Component Group Definition Commands"](#) on page 7-13.

Note: When working with component definition commands, start and run the `svrmgr` program for the enterprise. That is, do not start `svrmgr` with the `/s` or `-s` flag and do not run the command `set server`.

To create a new component

- Enter the following command:

```
create component definition component_alias_name for component type existing_component_type_alias_name
component group existing_component_group_alias_name
run mode run_mode
full name "component_full_name"
description "description_of_component"
with parameter parameter_alias_name=value
fixparam fixed_parameter_alias_name=fixed_value
```

The run mode options are:

- Batch
- Interactive
- Background

The component alias must be unique across the enterprise. The length of the alias name is dependent on the operating system.

You must enclose in quotes any keywords that you use in the component description, such as the keywords *for* or *component*. The alias or short name is required for the component group that you specify for this component definition. For a list of existing component groups and their corresponding aliases, see [Table A-2](#). For more information about component types, see "[About Server Component Types](#)" on page 2-7.

After running the `create` command, use the `activate component definition` command to enable the component definition at the enterprise, component definition level, and to enable and assign the component to the component group that you created. This action only occurs if the component definition is in the creating state. If the component definition is not in the creating state, then the command only enables the component definition at the enterprise level.

To activate a component definition

- After defining the component, activate the defined component by entering:

```
activate component definition component_alias_name
```

Note: If you receive an error when attempting to activate a new component definition, then make sure that you did not start the `svrmgr` command-line interface program by using the `/s` or `-s` flag, which targets only a specific server.

To deactivate a component definition

- Enter the following command:

```
deactivate component definition component_alias_name
```

To delete a component definition

- Enter the following command:

```
delete component definition component_alias_name
```

To copy a Siebel Server component definition

- Enter the following command:

```
copy compdef from source_comp_def_alias to target_comp_def_alias
```

Reconfiguring Component Definition Commands

To reconfigure component definitions, you must start the component reconfiguration, make the necessary configurations (for parameter configuration, see "[Parameter Management Commands](#)" on page 7-20), and then commit the reconfiguration. See the following procedures for these commands.

Caution: Review the background information about component definition reconfiguration before performing this task. For more information, see "[Reconfiguring Siebel Server Component Definitions](#)" on page 4-27.

To start a component definition reconfiguration

- Enter the following command:

```
reconfig compdef component_alias_name
```

To commit a component definition reconfiguration

- Enter the following command:

```
commit reconfig compdef component_alias_name
```

To cancel a component definition reconfiguration

- Enter the following command:

```
cancel reconfig compdef component_alias_name
```

Component Management Commands

Use component management commands to start or shut down Siebel Server components.

The startup `systemcomps`, shutdown `systemcomps`, startup `systemauxcomps`, shutdown `systemauxcomps`, startup `nonsystemcomps`, and shutdown `nonsystemcomps` commands manage the components in the System Management (alias System) component group or the Auxiliary System Management (alias SystemAux) component group, as follows:

- The components in the System component group include Server Manager, Server Request Broker, and Siebel Connection Broker.
- The components in the SystemAux component group include File System Manager, Server Request Processor, Server Tables Cleanup, and Siebel Administrator Notification Component.

To start a Siebel Server component

- Enter the following command:

```
startup component component_alias_name for server siebel_server_name
```

To shut down a Siebel Server component

- Enter the following command:

```
shutdown component component_alias_name for server siebel_server_name
```

To configure a Siebel Server component to start automatically

- Enter the following command:

```
auto start comp component_alias_name for server siebel_server_name
```

To start a Siebel Server component manually

- Enter the following command:

```
manual start comp component_alias_name for server siebel_server_name
```

To start Siebel Server components for the System component group

- Enter the following command:

```
startup systemcomps for server siebel_server_name
```

To shut down Siebel Server components for the System component group

- Enter the following command:

```
shutdown systemcomps for server siebel_server_name
```

To start Siebel Server components for the SystemAux component group

- Enter the following command:

```
startup systemauxcomps for server siebel_server_name
```

To shut down Siebel Server components for the SystemAux component group

- Enter the following command:

```
shutdown systemauxcomps for server siebel_server_name
```

To start Siebel Server components for all components except those in the System or SystemAux component group

- Enter the following command:

```
startup nonsystemcomps for server siebel_server_name
```

To shut down Siebel Server components for all components except those in the System or SystemAux component group

- Enter the following command:

```
shutdown nonsystemcomps for server siebel_server_name
```

Task Management Commands

Use task management commands to manage tasks for components running in batch or background mode.

You can start a new process by using the `start task` command or the `run task` command. Use the `start task` command if you plan to start multiple processes and use the `run task` command if you want to make sure that a process has run to completion.

The following are the two task management commands:

- **Start task.** The `start task` command starts a new process and allows you to execute a new command immediately. You are not notified of the task status, nor are you alerted if the task fails to perform. Instead, use the `list task` command to check the status of processes that were started by using the `start task` command.
- **Run task.** The `run task` command starts a new process that runs to completion (or exits with an error). You cannot execute a new command until the process has run to completion. The task status is displayed as the process is running.

To use multiple task parameters in a task command, list the parameters in a comma-separated list. The following example shows how to start a new process using various values for a given parameter:

```
start {task | server} for component component_alias_name with parameter_alias_
```

name=value1, value2, value3

To start a new task in batch mode

- Enter the following command:

```
start task for component component_alias_name server siebel_server_name with
parameter_alias_name1=value1, parameter_alias_name2=value2
```

This command starts a new task in batch mode and returns to the Siebel Server Manager immediately.

To start a new task in background mode

- Enter the following command:

```
start server for component component_alias_name server siebel_server_name with
parameter_alias_name1=value1, parameter_alias_name2=value2
```

This command starts a new task in background mode and returns to the Siebel Server Manager immediately.

To run a new task in batch mode

- Enter the following command:

```
run task for component component_alias_name server siebel_server_name with
parameter_alias_name1=value1, parameter_alias_name2=value2
```

This command runs a new task in batch mode to completion before returning to the Siebel Server Manager.

To pause a running task

- Enter the following command:

```
pause task task_ID for server siebel_server_name
```

Note: Only tasks from certain component types can be paused. For a list of these component types, see [Table 6-2](#).

To resume a paused task

- Enter the following command:

```
resume task task_ID for server siebel_server_name
```

To stop a running task

- Enter the following command:

```
stop task task_ID for server siebel_server_name
```

To terminate a running task using the kill command

- Enter the following command:

```
kill task task_ID for server siebel_server_name
```

The `kill task` command signals the Siebel Server to use operating system control to terminate the task. This command replicates the GUI procedure of clicking Menu and then Stop Task three times in succession on a running task.

Parameter Management Commands

Use the parameter management commands to change the values of a parameter.

To change an enterprise parameter

- Enter the following command:

```
change ent param parameter_alias_name1=value1, parameter_alias_name2=value2
```

To change a component definition parameter

- Enter the following command:

```
change parameter parameter_alias_name1=value1, parameter_alias_name2=value2 for  
compdef component_definition_name
```

To change a component type parameter

- Enter the following command:

```
change parameter parameter_alias_name1=value1, parameter_alias_name2=value2 for  
comptype component_type_name for server siebel_server_name
```

To change a Siebel Server parameter

- Enter the following command:

```
change parameter parameter_alias_name1=value1, parameter_alias_name2=value2 for  
server siebel_server_name
```

To change a component parameter

- Enter the following command:

```
change parameter parameter_alias_name1=value1, parameter_alias_name2=value2 for  
component component_alias_name server siebel_server_name
```

Note: If you started `svrMgr` with the `/s` or `-s` flag, then you do not have to include `server siebel_server_name` for this command.

To change a task parameter

- Enter the following command:

```
change parameter parameter_alias_name1=value1, parameter_alias_name2=value2 for  
task task_number
```

Note: After a server, component, or named subsystem parameter is modified, it ignores future parameter changes at higher levels. That is, future parameter changes at higher levels in the hierarchy do not cascade down to lower levels. Use the following commands to delete overrides and reinstate this functionality.

To delete an enterprise parameter override

- Enter the following command:

```
delete enterprise parameter override param parameter_alias_name
```

To delete a Siebel Server parameter override

- Enter the following command:


```
delete parameter override for server siebel_server_name param "parameter_alias_name"
```

To delete a named subsystem parameter override

- Enter the following command:

```
delete parameter override for named subsystem named_subsystem_alias_name param "parameter_alias_name"
```

To delete a server component parameter override

- Enter the following command:

```
delete parameter override for comp component_alias_name server siebel_server_name param "parameter_alias_name"
```

To delete a server component definition parameter override

- Enter the following command:

```
delete parameter override for compdef component_alias_name param "parameter_alias_name"
```

Named Subsystem Management Commands

Use named subsystem management commands to create, delete, and modify named subsystems. For more information about named subsystems, see ["About Named Subsystem Parameters"](#) on page 4-6 and ["Application Object Manager Named Subsystem Parameters"](#) on page 9-4.

To create a new named subsystem

- Enter the following command:

```
create named subsystem named_subsystem_alias_name for subsystem subsystem_alias_name with parameter_alias_name1=value1, parameter_alias_name2=value2
```

To delete a named subsystem

- Enter the following command:

```
delete named subsystem named_subsystem_alias_name
```

To list all named subsystem parameters

- For a particular named subsystem, enter the following command:

```
list parameters for named subsystem named_subsystem_alias_name
```

To list a particular named subsystem parameter

- Enter the following command:

```
list parameter parameter_alias_name for named subsystem named_subsystem_alias_name
```

To modify one or more named subsystem parameters

- Enter the following command:

```
change parameter parameter_alias_name1=value1, parameter_alias_name2=value2 for named subsystem named_subsystem_alias_name
```

System Alert Notification Commands

Use the following commands to configure system alert notification for server components. For more information about system alert notification, see "[About System Alert Notification](#)" on page 4-14.

To troubleshoot any problems with system alert notification, see "[Troubleshooting System Alert Notification](#)" on page 4-16.

To set the administrator email address

- Enter the following command:

```
change param AdminEmailAddress=Admin_Email_Address for named subsystem AdminEmailAlert
```

where *Admin_Email_Address* is the email address that receives the alert notification email.

To set the SMTP host and port number used for email notifications

- Enter the following command:

```
change param SMTPServer=SMTP_Server for named subsystem AdminEmailAlert
```

where *SMTP_Server* is the email server that routes the alert notification email.

To set the From email address

- Enter the following command:

```
change param FromAddress=Server_Email_Address for named subsystem AdminEmailAlert
```

where *Server_Email_Address* is the email address that sends the alert notification email.

To test the system alert notification

- Enter the following command:

```
start task for comp AdminNotify server Siebel_Server_Name
```

where *Siebel_Server_Name* is the name of the Siebel Server that hosts the AdminNotify server component.

List Definition Commands

Use list definition commands to list definitions for components, parameters, state values, and statistics.

To list component definitions

- For a particular component, enter the following command:

```
list component definitions for component component_alias_name
```

- For a particular task, enter the following command:

```
list component definitions for task task_number
```

List Parameter Override Commands

Use list parameter override commands to list parameter overrides for an enterprise, a Siebel Server, a component, a component definition, or a named subsystem.

For more information about parameter overrides, see ["About the Siebel Enterprise Server"](#) on page 2-3. See also ["Deleting System Parameter Overrides"](#) on page 4-31.

To list parameters for the enterprise

- Enter the following command:

```
list entparam overrides
```

To list parameters for a Siebel Server

- Enter the following command:

```
list param overrides for server siebel_server_name
```

To list parameters for a component

- Enter the following command:

```
list param overrides for comp component_alias_name server siebel_server_name
```

To list parameters for a component definition

- Enter the following command:

```
list param overrides for compdef component_definition_alias_name
```

To list parameters for a named subsystem

- Enter the following command:

```
list param overrides for named subsystem named_subsystem_alias_name
```

To list parameters for component definitions

- Enter the following command:

```
list param overrides for component component_alias_name
```

Event Logging Commands

Use the event logging commands to list event types for components and to change the values for event log levels. For more information about event logging, see *Siebel System Monitoring and Diagnostics Guide*.

To list event types

- Enter the following command:

```
list evtloglvl for component component_alias_name
```

To change the event log level for a component

- Enter the following command:

```
change evtloglvl event_alias_name=level for component component_alias_name
```

To change the event log level for a component on a Siebel Server

- Enter the following command:

```
change evtloglvl event_alias_name=level for server siebel_server_name component component_alias_name
```

To change the event log level for a Siebel Server

- Enter the following command:

```
change evtloglvl event_alias_name=level for server siebel_server_name
```

Server Manager Command-Line Preferences

You can create aliases for commands and configure list commands to return specific columns. These can be saved in a preferences file which is available to load the next time that you open a Siebel Server manager session. The preferences file is stored in the same directory as the Server Manager program. For the location of the Server Manager program, see ["Starting the Siebel Server Manager Command-Line Interface"](#) on page 7-1.

To create an alias for a command

- Enter the following command:

```
alias alias command_name
```

For example, the following command creates an alias `lc` for the command `list components`:

```
srvrmgr> alias lc list components
```

To delete an alias for a command

- Enter the following command:

```
unalias alias
```

To list the columns returned for a list command

- Enter the following command:

```
configure list_command
```

To configure a list command to show specific columns

- Enter the following command:

```
configure list_command show column1, column2, column3...
```

For example, the following command configures the `list components` command to return the component name column only.

```
srvrmgr> configure list components show CC_NAME
```

To configure a list command to show all columns

- Enter the following command:

```
configure list_command show all
```

For example, the following command configures the `list components` command to return all columns.

```
srvrmgr> configure list components show all
```

Note: The columns that are returned might not contain useful data. However, by using subsequent commands, you can specify which columns to display.

To save preferences

- Enter the following command:

```
save preferences
```

Preferences are saved in the same directory as the Server Manager program.

To load preferences

- Enter the following command:

```
load preferences
```

Siebel Server Infrastructure Administration

This chapter describes how to administer the Siebel Server infrastructure and system management components. It includes the following topics:

- [About Server Request Broker \(SRBroker\)](#)
- [Configuring Tasks for Server Request Broker](#)
- [About Server Request Processor \(SRProc\)](#)
- [About Siebel Connection Broker \(SCBroker\)](#)
- [About Other System Management Components](#)
- [Administering the Siebel File System](#)

About Server Request Broker (SRBroker)

Server Request Broker (alias SRBroker) is an interactive-mode Siebel Server component that belongs in the System Management component group. By default, one SRBroker is started for each Siebel Server. SRBroker handles client component requests by acting as a request router. For example, if a client makes a request to a Siebel Server for a component that is not running on that Siebel Server, then the request is routed to another Siebel Server that is running the requested component.

Siebel Server requests from clients that have no end point get stored in the database until the request is completed. The SRBroker works with the Server Request Processor (alias SRProc). For more information about this component, see "[About Server Request Processor \(SRProc\)](#)" on page 8-2.

SRBroker also controls how many component requests by clients can be serviced by a Siebel Server at one time. Each client connection and component connection counts as one task. The number of tasks that can be handled by a single SRBroker is determined by the Maximum Tasks (alias MaxTasks), Maximum MT Servers (alias MaxMTServers), and Minimum MT Servers (alias MinMTServers) component parameters. Keep MaxMTServers and MinMTServers at their default value of 1 for SRBroker. For more information about these parameters, see *Siebel Performance Tuning Guide*. For information about how to set the number of tasks for SRBroker, see "[Configuring Tasks for Server Request Broker](#)" on page 8-2.

Do not configure run-time parameters for SRBroker. If you have to support more client and component connections, then increase the number of tasks that can be handled by the SRBroker component.

Configuring Tasks for Server Request Broker

This topic describes how to configure the number of tasks for the Server Request Broker (alias SRBroker) component. For more information about SRBroker, see ["About Server Request Broker \(SRBroker\)"](#) on page 8-1.

To change the number of tasks that can be handled by Server Request Broker

1. Navigate to the Administration - Server Configuration, and then the Servers view.
2. In the Siebel Servers list, select the Siebel Server of interest.
3. Click the Components view tab.
4. In the Components list, query for Server Request Broker (alias SRBroker) in the Component field.
5. Select the Parameters view tab below the Components list.
6. In the Parameters list, query for the Maximum Tasks (alias MaxTasks) parameter.
7. In the Value on Restart field, type in the number of tasks.

The default value is 100. For more information about this parameter, see the parameter definition in ["Generic Parameters"](#) on page A-18. For more information about values to set this parameter, see *Siebel Performance Tuning Guide*.

8. For changes to take effect, restart the Siebel Server system service.

For more information about restarting the Siebel Server system service, see ["Administering the Siebel Server System Service"](#) on page 5-7.

About Server Request Processor (SRProc)

The Server Request Processor (alias SRProc) and the Server Request Broker (alias SRBroker) components are jointly responsible for the processing of both synchronous and asynchronous requests from a variety of Siebel Server components. SRProc is a background-mode component that handles requests between the Siebel Server and the database. There can only be one instance of SRProc for each Siebel Server. The following components rely on a functioning SRProc and SRBroker:

- Assignment Manager
- Communications Manager
- Enterprise Application Integration
- EIM
- Field Service (all components)
- Interactive Assignment
- Workflow Management

If either SRBroker or SRProc become unavailable for any reason, then the ability to execute intercomponent requests is severely affected. The request mechanism (component jobs) of the Server Manager GUI relies on a functioning SRBroker and SRProc to schedule and process requests. However, the server manager command-line interface program bypasses this request mechanism permitting the user to start (but not schedule) a component task by using the command-line interface if either or both the SRBroker or SRProc components are unavailable (or, alternatively, restarting the SRBroker or SRProc components). For more information about using the server manager command-line interface program, see [Chapter 7, "Using the Siebel Server Manager Command-Line Interface."](#)

Several parameters are available that ensure that these components automatically restart in the event of a failure, so the components experience as little downtime as possible. For information about the parameters Default Tasks (alias DfltTasks) and Auto-Restart (alias AutoRestart), see [Appendix A, "Siebel Server Components and Parameters."](#)

About Siebel Connection Broker (SCBroker)

The Siebel Connection Broker (alias SCBroker) component is a background-mode server component that provides intraserver load balancing. By default, it is always enabled and online. At least one instance of SCBroker must be running on any Siebel Server hosting interactive components.

Note: If a Siebel Server hosts only batch-mode components, then SCBroker can be disabled to prevent it from listening on a TCP port.

SCBroker listens on a configurable, static port for new connection requests from the Siebel Application Interface. The parameter Static Port Number (alias PortNumber) defines the port that SCBroker monitors. You specify this port number for SCBroker in the Siebel Management Console, when you configure the Siebel Server and when you configure the Siebel Application Interface. The default value is 2321. After a request is received, SCBroker distributes it to the appropriate instance of an Application Object Manager running on the Siebel Server.

The SCBroker component uses a connection forwarding algorithm to forward the socket to the Application Object Manager processes. The component parameter Connection Forward Algorithm for SCBroker (alias ConnForwardAlgorithm), which is a hidden parameter, has two possible settings:

- LL (for least-loaded algorithm)
- RR (for round-robin algorithm)

LL is the default value. The least-loaded algorithm balances incoming Application Object Manager login requests. It identifies which Application Object Manager process is handling the least number of tasks and assigns that process to handle the session. The round-robin algorithm distributes all of the Application Object Manager login requests to the next Application Object Manager process in a round-robin fashion, that is, equal loads distributed in order and without priority.

For more information about SCBroker and about load balancing, see *Siebel Deployment Planning Guide* and the *Siebel Installation Guide* for the operating system you are using.

About Other System Management Components

This topic describes the other server components that make up the System Management (alias System) and the Auxiliary System Management (SystemAux) component groups. It includes the following information:

- ["About Server Tables Cleanup \(SvrTblCleanup\)"](#) on page 8-4
- ["About Siebel Administrator Notification \(AdminNotify\)"](#) on page 8-4
- ["About Siebel Server Scheduler \(SvrSched\)"](#) on page 8-4

About Server Tables Cleanup (SvrTblCleanup)

Server Tables Cleanup (alias SvrTblCleanup) is a component that deletes the completed and expired Server Request records. The parameter Sleep Time (alias SleepTime) controls how often the cleanup occurs. The default value for Sleep Time is 300 seconds (5 minutes).

By default, the Server Tables Cleanup component is enabled on all of the Siebel Servers in your Siebel Enterprise Server. However, you only have to run one instance of this component, because it deletes the completed and expired server request records for all of the Siebel Servers in the Siebel Enterprise Server from the S_SRM_REQUEST table in the Siebel database. For this reason, you can disable other instances of this component on other Siebel Servers in the Siebel Enterprise Server.

The Server Tables Cleanup component is part of the Auxiliary System Management component group.

About Siebel Administrator Notification (AdminNotify)

Siebel Administrator Notification (alias AdminNotify) is a batch-mode component that notifies the Siebel administrator when problems are detected on the Siebel Server or its running components. For more information about component notification, see "[About System Alert Notification](#)" on page 4-14.

The Siebel Administrator Notification component is part of the Auxiliary System Management component group.

About Siebel Server Scheduler (SvrSched)

Siebel Server Scheduler (alias SvrSched) is a background-mode component supports the running of the Siebel Server and server components by spawning component processes as requested by the Siebel Server. No entries for the Siebel Server Scheduler component appear in the Siebel Server log file. Instead, entries appear for the component for which Siebel Server Scheduler spawns a process. A network message eventually assigns the process to the component it is supposed to run. The process loads the component and runs it. The Siebel Server Scheduler component is part of the System Management component group.

Caution: Do not modify the Siebel Server Scheduler component without instructions from Global Customer Support. For help modifying Siebel Server Scheduler, create a service request (SR) on My Oracle Support. Alternatively, you can phone Global Customer Support directly to create a service request or get a status update on your current SR. Support phone numbers are listed on My Oracle Support.

Note: Because of the nature of the Siebel Server Scheduler component, the Siebel Server Scheduler task IDs that appear in the log files do not have an appropriate entry in the Administration - Server Management screen. For the same reason, no entry appears in the Components view of the Administration - Server Configuration screen for this component.

Administering the Siebel File System

This topic provides background information and administration tasks applicable to the Siebel File System. This topic includes the following information:

- ["About the Siebel File System"](#) on page 8-5
- ["About the File System Upload and Download Process"](#) on page 8-6
- ["Partitioning the Siebel File System"](#) on page 8-7
- ["Cleaning Up the Siebel File System"](#) on page 8-10

About the Siebel File System

The Siebel File System is a shared directory or a set of directories that contain the physical files used by the Siebel clients. All of the File System directories must be network-accessible to the Siebel Server. You can create each File System directory on a server computer where you have installed a Siebel Server, or on another network server that can share the directory, so that the File System directories are available to the Siebel Server. For more information about the requirements for networked file systems, see the third-party documentation.

To gain access to files, Web clients connect to the appropriate Siebel Server to request file uploads or downloads. The Siebel Server then accesses the Siebel File System using the File System Manager (alias FSMSrvr) component. File System Manager processes these requests through interaction with the Siebel File System directories. For more information about data transfer, see ["About the File System Upload and Download Process"](#) on page 8-6.

At the server component level, most server components, including all Application Object Managers, access the Siebel File System through the File System Manager server component when administering attachments. Application Object Managers, however, access the Siebel File System directly when saving user preference files.

When using Siebel Developer Web Client for administrative tasks, you might want to connect directly to the Siebel File System without going through the File System Manager.

Files stored in the Siebel File System are compressed at the Siebel Server-level and appended with the extension .saf. (The file size displayed in the GUI represents the size of the compressed .saf file, not the actual file size.) The Siebel File System storage locations of the compressed files are set by the enterprise parameter Siebel File System (alias FileSystem). For more information about this parameter, see ["Siebel Enterprise Server Parameters"](#) on page A-15. The files stored in the Siebel File System are not directly accessible by users and must be retrieved (and decompressed) by the user through normal Siebel Web Client operations only.

Files stored in the Siebel File System are always compressed. That is, you cannot disable the compression feature of the Siebel File System.

You can exclude certain types of files from being saved into the Siebel File System, based on their file extensions. For more information about setting system preferences to enable this feature and to specify the file extensions to be excluded, see *Siebel Security Hardening Guide*.

Note: Virus checking is not supported within the Siebel File System.

This topic is part of ["Administering the Siebel File System"](#) on page 8-5.

Related Topics

["About the File System Upload and Download Process"](#) on page 8-6

["Partitioning the Siebel File System"](#) on page 8-7

["Cleaning Up the Siebel File System"](#) on page 8-10

Related Books

For information about creating the Siebel File System, see the *Siebel Installation Guide* for the operating system you are using.

For information about deployment options for the Siebel File System, see *Siebel Deployment Planning Guide*.

For information about securing the Siebel File System, see *Siebel Security Hardening Guide*.

About the File System Upload and Download Process

This topic describes what happens when files are uploaded to or downloaded from the Siebel File System.

This topic is part of ["Administering the Siebel File System"](#) on page 8-5.

About the File System Upload Transfer Process

When a user saves a file or attachment to be written to the Siebel File System, the file is copied from the user's hard drive and transferred to the Siebel Server. The data transfer protocol for file transfer matches that of the Web client browser to Siebel Application Interface, for example, HTTP or HTTPS. The File System Manager (alias FSMSrvr) component compresses the file, and then stores the compressed file in the Siebel File System. The compression and naming convention of the files is automated by FSMSrvr.

About the File System Download Transfer Process

When a Siebel application user accesses a file (for example, a PDF document) that is stored in the Siebel File System, a file or attachment download request is received by the FSMSrvr component of the Siebel Server. This component interacts with the Siebel File System directories to retrieve and send the compressed file back to the user's Web browser. As with the file upload process, the data transfer protocol for file transfer matches that of the Web client browser to Siebel Application Interface. The compressed file is decompressed by the user's Web browser, where the file can be reviewed or saved.

In some cases, the file is decompressed by the FSMSrvr component and sent to the user's Web browser in an uncompressed format. An uncompressed file is sent back to the Web browser in the following cases:

- The parameter Compressed File Download (alias CompressedFileDownload) is set to False. You configure this parameter in the Siebel Server Component Parameters view. For information about this task, see ["Configuring Siebel Server Component Parameters"](#) on page 4-21.
- The CompressedFileDownload parameter is set to False in the application configuration file for a Siebel Mobile Web Client. (If this parameter is not already in the configuration file, then you can add it to the [InfraUIFramework] section of the file.)

- The Web browser does not support compressed files, which is determined by looking at the request header.
- The file has the extension .zip, .z, .tgz, .gz, .gif, .jpg, or .jpeg.

Partitioning the Siebel File System

This topic describes how to perform the optional task of partitioning the Siebel File System.

This topic is part of "[Administering the Siebel File System](#)" on page 8-5.

About Partitioning the Siebel File System

Partitioning the Siebel File System allows you to store larger volumes of data on multiple devices. The original Siebel File System might use a single directory or might already use multiple directories on multiple devices or partitions.

In general, the term *partitioning*, as used in this topic, refers to running the `sfspartition` utility, which is provided for the purpose of adding one or more network directories to an existing Siebel File System and distributing the existing files among all of the participating directories. You can add each new directory on the same device as an existing directory or add it on a different device or partition in order to expand the overall capacity of the Siebel File System. (You must consider the future growth of the volume of data when you plan how to organize the file system directories.)

You can also use `sfspartition` to remove one or more existing directories from service for the Siebel File System, provided that the overall file system capacity remains sufficient.

To partition your Siebel File System, you first update the value of the enterprise parameter Siebel File System (alias FileSystem) so it specifies all of the network directories that you want to use for the Siebel File System, delimited by commas. You then run the partitioning utility and specify both the original directories containing the existing files and the updated target directories, corresponding to the updated FileSystem parameter value. The `sfspartition` utility distributes the files in the Siebel File System evenly across the target directories. The utility logs information into a file named `sfspartition.log`, which is located in the `log` directory within the Siebel Server root directory.

When the File System Manager component (alias FSMSrvr) starts, it verifies the existence of all of the file system directories specified using the FileSystem parameter. When new file attachments are inserted, FSMSrvr distributes them across these directories. If a file system directory is unavailable, then FSMSrvr logs an error message in the FSMSrvr log file and tries to write the file attachment to the next available directory. If no file system directory is available, then FSMSrvr terminates and writes an error message to the FSMSrvr log file.

In order to maintain the even distribution of files across file system directories, you must run the partitioning utility every time that you update the value of the FileSystem parameter, for example, if you add or remove a file system directory. The procedure in this topic describes in detail how to perform this task.

Before you partition your Siebel File System, note the following additional deployment options:

- **Mobile Web Client.** A Mobile Web Client's configuration file must refer to a single directory location, unless you configure it to use the server-based data source.

- **Replication Manager requirements.** Partitioning is supported on replicated nodes. For more information about replication, see *Siebel Remote and Replication Manager Administration Guide*.

Partitioning the File System Directories Using the `sfspartition` Utility

To partition the Siebel File System directories, run the partitioning utility `sfspartition`, as described in the following instructions.

The partitioning utility is named `sfspartition.exe` on Microsoft Windows or `sfspartition` on UNIX operating systems. This utility is located in the `bin` directory within the Siebel Server root directory.

Note: Where necessary, before you run the `sfspartition` utility, you must manually create any file system directories (such as the examples `siebelFS1`, `siebelFS2`, and `siebelFS3`, and so on) and subdirectories (such as `att`, `attmp`, and so on) on each target file system directory and grant the appropriate permissions to all of these directories. All of the file system directories must be accessible to all of the applicable Siebel Servers using the notation by which they are represented in the value of the `FileSystem` parameter.

For more information about creating a Siebel File System, see the *Siebel Installation Guide* for the operating system you are using.

To partition the file system directories using `sfspartition`

1. Where necessary, create any new directories or partitions that you will use with the Siebel File System, create required subdirectories, and grant the appropriate permissions to all of the directories. Then verify access to these directories.
2. Note the current value of the enterprise parameter Siebel File System (alias `FileSystem`) for later reference.

Note: You must note this value because you will use this information later when you specify the source directories by using the `/O` parameter when you run the `sfspartition` utility.

3. Set the value of the `FileSystem` parameter to include all of the directories that you want to use for the Siebel File System. Separate each directory with a comma (with no spaces), as in the examples that follow. Note the updated parameter value for later reference.

Note: You must note this value because you will use this information later when you specify the target directories by using the `/F` parameter when you run the `sfspartition` utility.

For example, on UNIX, you might specify this value:

```
/export/home/siebelFS1,/export/home/siebelFS2,/export/home/siebelFS3
```

For example, on Microsoft Windows, you might specify this value:

```
\\\\server1\\siebelFS1,\\\\server1\\siebelFS2,\\\\server2\\siebelFS3
```

Note: In this example, note that each backslash is doubled compared to the usual notation for such shared directories. For example, \\server1\siebelFS1 must be represented as \\\\server1\\siebelFS1. Alternatively, each file system directory can be represented using a mapped drive letter by which the directory can be accessed from each Siebel Server, such as D:\\siebelFS1 (note that each backslash must be doubled in this scenario also).

Caution: You must specify the file system directories in the same order for the FileSystem parameter and for the sfspartition utility. If you specify the directories using a different order, then the Siebel File System files might not be accessible after you use sfspartition.

4. If it is not already set, then set the ServerDataSrc named subsystem parameter DSFileSystem to *FSM*.

For information about configuring named subsystem parameters, see ["Configuring Siebel Enterprise Server Named Subsystem Parameters"](#) on page 4-11.

5. Restart the Siebel Server after updating the FileSystem and DSFileSystem parameter values.
6. Open a command prompt and change the directory to the bin subdirectory within the Siebel Server root directory.
7. Run sfspartition using parameters listed in [Table 8-1](#), as in the examples that follow.

The following example for UNIX distributes the files from one file system directory into three directories, corresponding to the updated value of the FileSystem parameter from Step 1 on page 8-8:

```
sfspartition /O /export/home/siebelFS /F
/export/home/siebelFS1,/export/home/siebelFS2,/export/home/siebelFS3 /H Y
```

Tip: Depending on how these network directories were created or mounted for use in UNIX environments, they might be on the same server or on different servers.

The following example for Microsoft Windows distributes the files from one file system directory on server1 into three directories on server1 and server2, corresponding to the updated value of the FileSystem parameter from Step 1 on page 8-8:

```
sfspartition /O \\server1\siebelFS /F
\\server1\siebelFS1,\\server1\siebelFS2,\\server2\siebelFS3 /H Y
```

Parameters for the sfspartition Utility

[Table 8-1](#) describes the parameters for the sfspartition utility.

Table 8–1 Parameters for *sfspartition* Utility

Parameter	Value	Description	Required?
/O	<i>Paths for existing source directories</i>	<p>Set this value to the paths of the existing source directories for the file system. Separate multiple directories using commas, with no spaces. If any of the paths themselves contain a space, then enclose the parameter value in double quotes.</p> <p>Whether you must append <code>att</code> to each source directory depends on how you use the /H parameter:</p> <ul style="list-style-type: none"> ▪ If you use /H Y, then do not append <code>att</code> to each source directory that you specify by using /O. (The purpose of /H Y is to eliminate the need to append <code>att</code>.) ▪ If you use /H N (or omit /H), then you must append <code>att</code> to each source directory that you specify by using /O. The utility looks both in the specified source directories and in the <code>att</code> subdirectories to find the files to be distributed to the specified target directories. 	Yes
/F	<i>Paths for target directories</i>	<p>Set this value to the paths of the target directories for the file system. Separate multiple directories using commas, with no spaces. If any of the paths themselves contain a space, then enclose the parameter value in double quotes. (Use the same value as the value of the <code>FileSystem</code> parameter.)</p> <p>Whether you must append <code>att</code> to each target directory depends on how you use the /H parameter:</p> <ul style="list-style-type: none"> ▪ If you use /H Y, then do not append <code>att</code> to each target directory that you specify by using /F. (The purpose of /H Y is to eliminate the need to append <code>att</code>.) ▪ If you use /H N (or omit /H), then you must append <code>att</code> to each target directory that you specify by using /F. Otherwise, files will not be distributed to the <code>att</code> subdirectories of the target directories and will be inaccessible to clients. 	Yes
/H	Y or N	<p>Set /H Y if you want the utility to automatically append <code>att</code> to each source and target directory that you specify by using /O and /F. (Do not append <code>att</code> when you specify these directories.)</p> <p>Set /H N (or omit /H) if you do not want the utility to automatically append <code>att</code> to each source and target directory that you specify by using /O and /F. (Append <code>att</code> when you specify these directories.)</p>	No

Cleaning Up the Siebel File System

This topic describes how to clean up the Siebel File System by removing orphan records using the Siebel File System cleanup utility, `sfscleanup`. Orphan records are those that remain if a user deletes a parent record in the application that has associated child records. The child records are not deleted from the Siebel File System with the parent record and so you must remove them by using file system cleanup utility.

The Siebel File System cleanup utility is named `sfscleanup.exe` on Microsoft Windows or `sfscleanup` on UNIX operating systems. This utility is located in the `bin` directory within the Siebel Server root directory.

The `sfsfcleanup` utility processes records for every file in the file attachment directories (the `att` subdirectories) of the specified Siebel File System directories and performs one of several operations to each record and file, depending on the file type and on the parameters that you set. Optionally, you can run `sfsfcleanup` for a limited period of time and resume the operation again later.

For descriptions of the run-time parameters that you can set when running `sfsfcleanup`, see [Table 8-2](#). More information about some of the parameters follows the table. For descriptions of the file types and the associated operation performed by `sfsfcleanup` during processing, see [Table 8-3](#).

This topic is part of "[Administering the Siebel File System](#)" on page 8-5.

To clean up the file attachment directory using `sfsfcleanup`

1. At the command prompt, change directory to the `bin` subdirectory within the Siebel Server root directory.
2. Run `sfsfcleanup` using parameters listed in [Table 8-2](#), in a command like the following example:

```
sfsfcleanup /U sadmin /P pwd /F \\server1\files /X \\server1\logs\sfsfcleanup.log
```

Parameters for the `sfsfcleanup` Utility

[Table 8-2](#) describes the parameters for the `sfsfcleanup` utility. More information about some of the parameters is provided after the table.

Table 8-2 Parameters for `sfsfcleanup` Utility

Parameter	Value	Description	Required?
<code>/U</code>	<i>Username</i>	User name ID.	Yes
<code>/P</code>	<i>Password</i>	User name password.	Yes
<code>/C</code>	<i>ODBC_data_source</i>	Set this value to the ODBC data source. The default value is the setting of the environment variable <code>SIEBEL_DATA_SOURCE</code> .	No
<code>/D</code>	<i>Siebel_table_owner</i>	Set this value to the Siebel table owner. The default value is the setting of the environment variable <code>SIEBEL_TABLE_OWNER</code> .	No
<code>/F</code>	<i>Paths for file system directories</i>	Set this value to the paths for the file system directories. Separate multiple directories using commas, with no spaces. If any of the paths themselves contain a space, then enclose the parameter value in double quotes. (Use the same value as the value of the <code>FileSystem</code> parameter.) Whether you must append <code>att</code> to each directory depends on how you use the <code>/H</code> parameter: <ul style="list-style-type: none"> ▪ If you use <code>/H Y</code>, then do not append <code>att</code> to each directory that you specify using <code>/F</code>. (The purpose of <code>/H Y</code> is to eliminate the need to append <code>att</code>.) ▪ If you use <code>/H N</code> (or omit <code>/H</code>), then you must append <code>att</code> to each directory that you specify using <code>/F</code>. The utility looks both in the specified directories and in the <code>att</code> subdirectories to find the files to be cleaned up. 	Yes

Table 8–2 (Cont.) Parameters for sfscleanup Utility

Parameter	Value	Description	Required?
/X	<i>Path for output file</i>	Set this value to the path for the output file.	No
/M	<i>Path for move directory</i>	Set this value to the path for the directory where discarded files are to be moved.	No
/N	Y or N	Determines whether old versions of file attachments are to be removed. To remove old versions, set this value to Y. The default value is N.	No
/R	Y or N	Set this value to Y to generate only a report file. If it is set to Y, then the report file contains only the columns File Name and File Type. The default value is N.	No
/H	Y or N	Set /H Y if you want the utility to automatically append <i>att</i> to each directory that you specify using /F. (Do not append <i>att</i> when you specify these directories.) Set /H N (or omit /H) if you do not want the utility to automatically append <i>att</i> to each directory that you specify using /F. (Append <i>att</i> when you specify these directories.)	N
/G	Y or N	Set this value to remove garbage files or non-Siebel files. The default value is N.	No
/Q	Y or N	Set /Q Y if you want the utility to perform a query by file attachment records. This parameter allows you to run the utility for a limited period of time and provides other ways to manage how the utility runs. The default value is N. Note: When you are using /Q Y, you can also use the parameters /I, /O, /S, and /T. Otherwise, these parameters have no effect.	N
/I	<i>Number of file IDs</i>	Set /I to the number of file attachment records to query. The default value is 300. The utility processes records and files in batches based on the specified number of records. After those files have been processed, the utility processes more records and files in another batch. Note: This parameter has an effect only if you are using /Q Y.	N
/O	Y or N	Use /O Y when you want the utility to use an OR clause to constrain the query row IDs, like this: (ROW_ID = 'Id1' OR ROW_ID = 'Id2' OR ...). The default value is Y. Use /O N to instead use a clause like this: ROW_ID IN ('Id1', 'Id2', ...). Note: This parameter has an effect only if you are using /Q Y. It determines the internal query executed in Siebel database. No row ID is entered as an argument.	N

Table 8–2 (Cont.) Parameters for sfscleanup Utility

Parameter	Value	Description	Required?
/S	Y or N	Use /S Y to resume the previous run, from the next unprocessed record, where information about the last processed record is available in a temporary directory. The default value is N. Use /S N (or omit /S) to instead start a new run. Note: This parameter has an effect only if you are using /Q Y.	N
/T	<i>Number of minutes</i>	Set /T to the number of minutes to run the query. When the utility reaches that time, the last processed file attachment record is noted in a temporary directory and the utility exits. Later, you can resume the previous run by using /S Y. By default, the utility runs to completion, until all of the records and files are processed. Note: This parameter has an effect only if you are using /Q Y.	N

More Information About Some sfscleanup Parameters

The following provides more information about some of the parameters for the sfscleanup utility. The parameters are described in [Table 8–2](#).

- **/N.** By default, old file revisions are kept. Such files are marked ANCIENT in the log, and represent old revisions of an existing attachment record. That is, their row ID matches with the database record but not the file revision number. To delete such files, set the /N parameter to Y.
- **/G.** If the file system contains files that were not created by the File System Manager component (alias FSMSrvr), then their deletion or move is controlled by the /G parameter. This parameter includes non-Siebel files or directories. By default these files are not deleted. The directories are not affected or moved by sfscleanup.
- **/Q.** By default, the sfscleanup utility processes all of the files in the file attachment directories in a single long-running operation. For a Siebel File System that includes a very large number of files, such an operation might affect performance or inconvenience production users.

Alternatively, the /Q parameter allows you, for example, to process files in batches based on a query of a given number or file attachment records (by using /I), to modify how the utility queries these records (by using /O), to run the utility for a specific period of time (by using /T), and to resume a run later where it left off (by using /S). For example, you might decide to run the sfscleanup utility only when most of your users are not logged in. For more information, see the descriptions in [Table 8–2](#).

About the sfscleanup Log File

If you specified an output file using the /X parameter, then sfscleanup generates a log file listing the operations that were performed. The output file is a tab-delimited text file that contains the following columns:

- **File Name.** This column lists the name of each file that was processed.

- File Type.** This column lists the type of each file that was processed. [Table 8-3](#) lists the possible file types and the associated operation performed by `sfsfcleanup` during processing. For descriptions of each operation, see [Table 8-4](#).

Table 8-3 File Types and Associated Operations for `sfsfcleanup` Utility

File Type	Description	Operation
CURRENT	The file has a corresponding record in the file attachment database table.	KEPT
NEW	The file is less than one hour old. The <code>sfsfcleanup</code> utility does not check for the file in the file attachment database table.	KEPT
ORPHAN	The file does not have a corresponding record in the file attachment database table. If you used the <code>/M</code> parameter to set a move directory, then the operation performed is <code>MOVED</code> , not <code>DELETED</code> .	DELETED
INVALID	The file (or directory) is not a file attachment. If <code>sfsfcleanup</code> tries to delete a subdirectory that is not empty, then the operation errors out. Review the files contained within the directory before deleting them. If you set the <code>/G</code> parameter to <code>Y</code> , then the operation performed is <code>DELETED</code> , not <code>KEPT</code> .	KEPT
ANCIENT	The file has an associated record in the database with a different revision number. If you set the <code>/N</code> parameter to <code>Y</code> , then the operation performed is either <code>MOVED</code> (if you used the <code>/M</code> parameter to set a move directory) or <code>DELETED</code> , not <code>KEPT</code> .	KEPT

- Operation.** This column lists the type of operation that was performed during processing. [Table 8-4](#) lists the types of operation that `sfsfcleanup` might have performed during processing.

Table 8-4 Operations for `sfsfcleanup` Utility

Operation	Description
KEPT	The file was kept.
DELETED	The file was deleted.
MOVED	The file was moved to the directory specified by the <code>/M</code> parameter. Files are moved if you used the <code>/M</code> parameter.
KEPT_DIR	The item was kept because it was a directory and requires manual processing.
KEPT_ERROR	The file was kept because an error occurred while trying to move or delete the file.

Application Object Manager Administration

This chapter explains how to configure, deploy, and administer Application Object Managers to support Siebel Web Clients. This chapter also explains Application Object Manager concepts to provide useful background information. It includes the following topics:

- [About the Siebel Application Object Manager](#)
- [Configuring the Application Object Manager Environment](#)
- [About Application Object Manager Parameters](#)
- [Administering the Application Object Manager](#)

About the Siebel Application Object Manager

Siebel Application Object Manager (Application Object Manager) components host the Business Objects layer and Data Objects layer of the Siebel architecture. The Siebel Web Clients host the Siebel application user interface layer. The Application Object Manager supports Siebel Web Client connections and handles multiple users simultaneously by making requests to the Siebel Server on behalf of the clients.

Application Object Managers are hosted as components in the installed Siebel Server and run on the Siebel Server computer (sometimes called the application server computer). The Siebel Server provides the infrastructure for an Application Object Manager to serve multiple Siebel Web Client users. Multiple Application Object Manager components can run on a single Siebel Server installation. Application Object Manager components can be configured to run as multithreaded processes in the Siebel Server. Like other Siebel Server components, you can administer Application Object Manager components using the Siebel Server Manager.

Application Object Managers communicate with clients using the TCP/IP protocol through the Siebel Application Interface. Communication between the Siebel Application Interface and the Application Object Manager can be compressed and encrypted. An independent session is established to serve incoming connect requests from each client. Subsequent requests from clients are directed to the same Application Object Manager tasks until the sessions are terminated.

After startup, Application Object Managers do not achieve their full run-time environments until after the first connect, therefore, leading to possible delays during the first connection. For more information about how the Siebel Web Clients and Application Object Managers communicate, see *Siebel Performance Tuning Guide*.

The Siebel runtime repository is installed as part of each Siebel database installation. User preferences set and saved by Siebel Web Client users are saved on the Siebel Server.

Note: If you are running the Siebel Server in a UNIX environment, then Application Object Managers support Siebel eScript, but not Siebel Visual Basic.

About Application Object Manager Memory Allocation

The Application Object Manager caches information in two different ways. Some information is cached and used by every connection and other information is stored for each user connection.

Memory allocation for the Application Object Manager can be broken into three areas:

- **User memory.** The user area maintains specific information about each user's session. Typically, each user uses 3 MB to 4 MB of memory, although the memory required depends on the Siebel application in use. This memory is released when the task is completed.
- **Shared memory between users.** Shared memory is for common structures used by every user and is the largest segment of Application Object Manager memory. It contains definitions for business objects, business components, controls, and other metadata items from the Siebel repository. This memory is loaded as needed and remains loaded for the life of the process. Application Object Manager processes commonly use more than 150 MB.
- **Administrative memory.** The administrative area of memory used by Application Object Manager manages the component itself. This memory is relatively small and is used to manage communication between the Application Object Manager and other Siebel Server components. It runs the listener and coordinates threads and tasks.

Configuring the Application Object Manager Environment

This topic describes how to configure the environment for your Application Object Manager components.

To configure the Application Object Manager environment

1. Make sure that Application Object Managers are included as part of the Siebel Server installations you plan to use.

Configuring a Siebel Server defines the Application Object Manager components for this Siebel Server. For information about installing and initially configuring the Siebel Server, see the *Siebel Installation Guide* for the operating system you are using.

2. Verify that the customized Siebel runtime repository is included in the Siebel database that serves the modified application.

It is strongly recommended that no other user besides the application developer customize the Siebel runtime repository.

3. Configure the Application Object Manager components by setting the parameters that control:
 - Application name to run (configuration file)
 - Language code
 - Compression setting
 - Encryption setting

- Number of processes for each component
- Number of threads or tasks for each process
- Session Manager parameters

For more information about this topic, see ["About Application Object Manager Parameters"](#) on page 9-3.

4. Restart the Siebel Server system service to automatically register the Application Object Manager services (configured in Step 3).

About Application Object Manager Parameters

At startup, Application Object Manager components accept several parameters that determine their behavior. Parameters that affect the operation of Application Object Managers can be modified in:

- Component parameters for the Application Object Manager using the Siebel Server Manager. For more information about this task, see ["Configuring Siebel Server Component Parameters"](#) on page 4-21.
- Named subsystem parameters using Siebel Server Manager. For more information about this task, see ["Configuring Siebel Enterprise Server Named Subsystem Parameters"](#) on page 4-11.

Application Object Manager Parameters in Server Manager

This topic provides a partial list of component-specific and generic parameters you set for the Application Object Manager. You configure Application Object Manager parameters in the same manner as those for any server component. To configure Application Object Manager parameters using the Server Manager GUI, see ["Configuring Siebel Server Component Parameters"](#) on page 4-21. To configure Application Object Manager parameters using the Server Manager command-line interface, see ["Parameter Management Commands"](#) on page 7-20.

See the following parameters:

- Compression Type (alias Compress)
- Encryption Type (alias Crypt)
- Error Flags (alias ErrorFlags)
- Language Code (alias Lang)
- Log Print Timestamp (alias LogTimestamp)
- Maximum MT Servers (alias MaxMTServers)
- Maximum Tasks (alias MaxTasks)
- Minimum MT Servers (alias MinMTServers)
- Multi-Threaded (alias Threaded)
- Number of lines after which to flush the log file (alias LogFlushFreq)
- Password (alias Password)
- Trace Flags (alias TraceFlags)
- User Name (alias Username)
- Use Shared Log File (alias LogUseSharedFile)

For a description of each parameter, see ["Siebel Enterprise, Server, and Component Parameters"](#) on page A-11.

For information about locale-specific Application Object Manager parameters, including information about regional standards for currency, time, date, and so on, see *Siebel Global Deployment Guide*.

Application Object Manager Named Subsystem Parameters

The Application Object Manager can maintain several different values for a particular parameter by using named subsystems. For more information about named subsystems and named subsystem parameters, see ["About Named Subsystem Parameters"](#) on page 4-6. For information about configuring Application Object Manager named subsystem parameters, see ["Configuring Siebel Enterprise Server Named Subsystem Parameters"](#) on page 4-11.

Named Subsystems Used by Application Object Managers

[Table 9-1](#) provides a partial list of named subsystems used by Application Object Managers.

Table 9-1 *Named Subsystems Used by Application Object Managers*

Named Subsystem	Alias	Type	Description
DataMart Datasource	DataMart	InfraDatasources	Datamart data source used by Application Object Manager components
Gateway Datasource	GatewayDataSrc	InfraDatasources	Gateway data source used by Application Object Manager components
Object Manager Cache	ObjMgrCache	InfraObjMgrCache	Cache parameters for Application Object Manager components
Server Datasource	ServerDataSrc	InfraDatasources	Server data source used by Application Object Manager components
LDAP Security Adapter	LDAPSecAdpt	InfraSecAdpt_ LDAP	LDAP security adapter used for Application Object Manager authentication with directory servers

Named Subsystem Parameters

[Table 9-2](#) provides a partial list of named subsystem parameters.

Table 9–2 *Named Subsystem Parameters*

Parameter Alias	Named Subsystem	Data Type	Description
DSConnectString	GatewayDataSrc	String	<p>Specifies the host name of the Siebel Gateway.</p> <p>The value \$(GatewayAddress) for the parameter ConnectString of the GatewayDataSrc section of the Application Object Manager's configuration file is replaced at run time with the value for the named subsystem parameter DSConnectString. An incorrect setting for DSConnectString results in server administration being inaccessible from the Siebel Web Client.</p>
DSConnectString	ServerDataSrc	String	<p>Specifies the database connection information. On Oracle Database (native), this information is the TNS alias from tnsnames.ora. On Microsoft SQL Server and IBM DB2, this information is the ODBC Datasource Name.</p>
DSDockedFlg	ServerDataSrc	Boolean	<p>When you create a new named subsystem for an Application Object Manager, you must set this parameter to True.</p>
DSFileSystem	ServerDataSrc	String	<p>Set this parameter to *FSM* to allow the use of the File System Manager server component for standard Siebel Web Clients.</p>
DSMaxCursorSize	ServerDataSrc, GatewayDataSrc, or DataMart	Integer	<p>Sets the total number of rows that can be returned in a result set.</p> <p>The parameter MaxCursorSize is set for the Application Object Manager component by using the named subsystem parameter DSMaxCursorSize. (The applicable subsystem corresponds to the component parameter OM - Data Source.) This parameter is valid only with IBM DB2 for OS/390 and z/OS.</p> <p>For more information, see the description of the MaxCursorSize parameter in "Parameters for Individual Data Source Sections" on page B-12.</p>

Table 9–2 (Cont.) Named Subsystem Parameters

Parameter Alias	Named Subsystem	Data Type	Description
DSPreFetchSize	ServerDataSrc, GatewayDataSr, or DataMart	Integer	<p>Sets the number of rows that the Siebel application reads initially as part of a query execution.</p> <p>The parameter PreFetchSize is set for the Application Object Manager component by using the named subsystem parameter DSPreFetchSize. (The applicable subsystem corresponds to the component parameter OM - Data Source.) This parameter is valid only with IBM DB2 for OS/390 and z/OS.</p> <p>For more information, see the description of the PreFetchSize parameter in "Parameters for Individual Data Source Sections" on page B-12.</p>
DSEnterpriseServer	ServerDataSrc, GatewayDataSr	String	Specifies the name of the Siebel Enterprise Server used by various named subsystems. The value in the Application Object Manager is replaced at run time with the value set for the named subsystem.
DSRequestServer	ServerDataSrc	String	Specifies where asynchronous calls are redirected, for example when using Interactive Assignment. Set this value to the logical name of the Siebel Server, not the computer name. The default value is null.
DSTableOwner	All named subsystems of type InfraDatasources	String	Specifies the table owner for this data source. Application Object Manager server components, such as Call Center Object Manager, read the value of this parameter. Siebel Server infrastructure and system management components, such as Server Request Broker (SRBroker), read the value of the TableOwner enterprise parameter.
DSDisableExecuteRetry	ServerDataSrc	Boolean	When set to True, this parameter prevents the Application Object Manager from resending a query to the database layer if an error occurs such as a network error or session kill.

To configure named subsystems using the Siebel Server Manager command-line interface, see ["Named Subsystem Management Commands"](#) on page 7-21.

Administering the Application Object Manager

You can monitor Application Object Managers at the following levels:

- The server level using Siebel Server
- The component level using Application Object Manager components
- The task level using Application Object Manager tasks

At each of these levels, you can do the following:

- Use the server administration views to monitor the following:
 - State values
 - Statistics
 - Log files
- Use the Siebel Server Component Parameters view to set the component-specific parameters for the Application Object Manager.
- Start, stop, pause, or resume any Application Object Manager tasks.

For more information about Application Object Manager state values, statistics, and log files, and about monitoring an Application Object Manager server component, see *Siebel System Monitoring and Diagnostics Guide*.

At the component event level, you can enable SQL tracing to view the SQL that is generated for the specified Application Object Manager. You can enable SQL spooling on the Application Object Manager task by setting the Object Manager SQL Log event parameter to 4 at the component event level. For more information about event logging, see "[Event Logging Commands](#)" on page 7-23. See also *Siebel System Monitoring and Diagnostics Guide*.

Siebel Server Components and Parameters

This appendix identifies the Siebel Server component groups and components and describes some of the server parameters that you might have to set. It includes the following topics:

- [Siebel Server Component Groups](#)
- [Siebel Server Components](#)
- [Siebel Enterprise, Server, and Component Parameters](#)

Siebel Server Component Groups

[Table A-1](#) lists some of the predefined Siebel Server component groups and the components they include. Many of the components, such as Application Object Manager components, are language-specific, although in most cases the language-specific names are not shown in this table.

Table A-1 *Predefined Siebel Server Component Groups*

Component Group Name	Alias	Component Name	Alias
Assignment Management	AsgnMgmt	Batch Assignment	AsgnBatch
		Assignment Manager	AsgnSrvr
Auxiliary System Management	SystemAux	File System Manager	FSMSrvr
		Server Request Processor	SRProc
		Server Tables Cleanup	SvrTblCleanup
		Server Task Persistence	SvrTaskPersist
		Siebel Administrator Notification Component	SCCObjMgr
Siebel Call Center	CallCenter	Call Center Object Manager	SCCObjMgr
		Self Service Object Manager	SServiceObjMgr

Table A-1 (Cont.) Predefined Siebel Server Component Groups

Component Group Name	Alias	Component Name	Alias
Communications Management	CommMgmt	Communications Inbound Processor	CommInboundProcessor
		Communications Inbound Receiver	CommInboundRcvr
		Communications Session Manager	CommSessionMgr
		Communications Configuration Manager	CommConfigMgr
		Communications Outbound Manager	CommOutboundMgr
		Email Manager	MailMgr
		Page Manager	PageMgr
		Smart Answer Manager	SmartAnswer
Content Center	ContCtr	Content Project Publish	ContProjPub
		Content Project Start	ContProjStart
Dun and Bradstreet	DandB	D&B Update Mgr (D&B)	DBNUpMgrDNB
		D&B Update Mgr (Multi-task)	DNBUpMgrMultiTask
		D&B Update Mgr (Siebel)	DNBUpMgrSieb
Data Quality	DataQual	Data Quality Manager	DQMgr
Enterprise Application Integration	EAI	Custom Application Object Manager	CustomAppObjMgr
		Enterprise Integration Mgr	EIM
		EAI Object Manager	EAIObjMgr
		JMS Receiver	JMSReceiver
		MQSeries Server Receiver	MqSeriesSrvRcvr
		MQSeries AMI Receiver	MqSeriesAMIRcvr
		MSMQ Receiver	MSMQRcvr
Siebel eChannel	eChannel	Partner Manager Object Manager	PManagerObjMgr
		Siebel Partner Portal Object Manager	PartnerPortalObjMgr
		eChannel Object Manager	eChannelObjMgr
Siebel eDocuments	eDocuments	Document Server	DocServer
Forecast Service Management	FcstSvc	Forecast Service Manager	FcstSvcMgr

Table A-1 (Cont.) Predefined Siebel Server Component Groups

Component Group Name	Alias	Component Name	Alias
Field Service	FieldSvc	Field Service Cycle Counting Engine	FSCycCnt
		Service Order Fulfillment Engine	FSFulfill
		Field Service Mobile Inventory Transaction Engine	FSInvTxn
		Service Order Part Locator Engine	FSLocate
		Preventive Maintenance Engine	FSPrevMnt
		Field Service Replenishment Engine	FSRepl
		Appointment Booking Engine	ApptBook
		Optimization Engine	Optimizer
		Field Service Object Manager	SFSObjMgr
Handheld Synchronization	HandheldSync	Sales Mobile Object Manager	SalesmObjMgr
		Service Mobile Object Manager	ServicemObjMgr
Handheld Synchronization SIA	HandheldSyncSIS	eCG Sales Mobile Object Manager	CGMObjMgr
		ePharma Mobile Object Manager	ePharmaMObjMgr
		FINS Mobile Object Manager	FINSMObjMgr
Siebel ISS	ISS	Siebel Product Configuration Object Manager	eProdCfgObjMgr
		eSales Object Manager	eSalesObjMgr
		eCustomer Object Manager	eCustomerObjMgr
Marketing Object Manager	MktgOM	Marketing Object Manager	SObjMgr
		eMarketing Object Manager	eMarketObjMgr
		eEvents Object Manager	eEventsObjMgr
Marketing Server	MktgSrv	List Import Service Manager	ListImportSvcMgr
Disconnected Mobile Synchronization	MobileSync	BatchSync	BatchSync
		Database Extract	DbXtract
		Mobile Data Extraction	MobileDbXtract
		Parallel Database Extract	PDbXtract
		Transaction Processor	TxnProc
		Transaction Router	TxnRoute
PIM Server Integration Management	PIMSI	PIMSI Engine	PIMSIEng
		PIMSI Dispatcher	PIMSIDispatcher
Sales Hierarchy Service	SalesHierSvc	Sales Hierarchy Service Manager	SalesHierSvcMgr
Search Processing	Search	Search Data Processor	SearchDataProcessor
		Search Incremental Index Processor	SearchIncrementalIndexProcessor

Table A-1 (Cont.) Predefined Siebel Server Component Groups

Component Group Name	Alias	Component Name	Alias
Siebel Remote	Remote	Generate New Database	GenNewDb
		Replication Agent	RepAgent
		Synchronization Manager	SynchMgr
		Transaction Merger	TxnMerge
Siebel RTI	RTI	RTI Batch	RTIBatch
Siebel Sales	Sales	Sales Object Manager	SSEObjMgr
Siebel Anywhere	SiebAnywhere	Upgrade Kit Builder	UpgKitBldr
Siebel Web Tools	SiebelWebTools	Siebel Web Tools Object Manager	SWToolsObjMgr
System Management	System	Server Manager	ServerMgr
		Server Request Broker	SRBroker
		Siebel Connection Broker	SCBroker
		Siebel Server	SiebSrvr
		Siebel Server Scheduler	SrvrSched
Task UI	TaskUI	Task Log Cleanup	TaskLogCleanup
Territory Management	TerritoryMgmt	Minor Alignment - Territory Rules Merge Manager	MinTerrMergeMgr
		Major Alignment - Territory Rules Merge Manager	MajTerrMergeMgr
Workflow Management	Workflow	Generate Triggers	GenTrig
		Workflow Monitor Agent	WorkMon
		Workflow Process Batch Manager	WfProcBatchMgr
		Workflow Process Manager	WfProcMgr
		Workflow Action Agent	WorkActn
		Workflow Recovery Manager	WfRecvMgr

Siebel Server Components

[Table A-2](#) lists some of the predefined Siebel Server components. Many of the components, such as Application Object Manager components, are language-specific, although in most cases the language-specific names are not shown in this table.

Table A–2 *Predefined Siebel Server Components*

Component Name	Alias	Mode	Multi-threaded	Description
Appointment Booking Engine	ApptBook	Batch	Yes	Books appointments. For more information, see <i>Siebel Field Service Guide</i> .
Assignment Manager	AsgnSrvr	Batch	Yes	Automatic data assignment engine that assigns positions, employees, and organizations to objects. To run Interactive Assignment, the Server Request Processor component must also be running. For more information, see <i>Siebel Assignment Manager Administration Guide</i> .
Batch Assignment	AsgnBatch	Batch	No	Batch assigns positions, employees, and organizations to objects. For more information, see <i>Siebel Assignment Manager Administration Guide</i> .
BatchSync	BatchSync	Batch	No	Extracts user databases for Siebel Mobile disconnected, processes pending transactions, and applies transactions to the Siebel Server. For more information, see <i>Siebel Mobile Guide: Disconnected</i> .
Call Center Object Manager	SCCObjMgr	Interactive	Yes	Application Object Manager for Siebel Call Center.
Communications Configuration Manager	CommConfigMgr	Batch	Yes	Downloads and caches communications configuration. For more information, see <i>Siebel CTI Administration Guide</i> .
Communications Inbound Processor	CommInboundProcessor	Batch	Yes	Processes queued communication events. For more information, see <i>Siebel Email Administration Guide</i> .
Communications Inbound Receiver	CommInboundRcvr	Batch	Yes	Queues inbound communication events. For more information, see <i>Siebel Email Administration Guide</i> .
Communications Outbound Manager	CommOutboundMgr	Batch	Yes	Sends messages to recipients associated with business object instances. For more information, see <i>Siebel Email Administration Guide</i> .
Communications Session Manager	CommSessionMgr	Batch	Yes	Interacts with users for utilizing communications channels. For more information, see <i>Siebel CTI Administration Guide</i> .
Content Project Publish	ContProjPub	Batch	Yes	Publishes a content project.
Content Project Start	ContProjStart	Batch	Yes	Starts a content project.
Custom Application Object Manager	CustomAppObjMgr	Interactive	Yes	Siebel Custom Application Object Manager.
D&B Update Mgr (D&B)	DNBUpmgrDNB	Batch	No	Updates D&B tables with subscription data. For more information, see <i>Siebel Applications Administration Guide</i> .

Table A–2 (Cont.) Predefined Siebel Server Components

Component Name	Alias	Mode	Multi-threaded	Description
D&B Update Mgr (Multi-task)	DNBUpMgrMultiTask	Batch	Yes	Creates multiple D&B Update Mgr (D&B) or D&B Update Mgr (Siebel) processes by sending asynchronous requests. For more information, see <i>Siebel Applications Administration Guide</i> .
D&B Update Mgr (Siebel)	DNBUpMgrSieb	Batch	No	Updates Siebel database tables with subscription data. For more information, see <i>Siebel Applications Administration Guide</i> .
Data Quality Manager	Dqmgr	Batch	Yes	Cleanses data and deduplicates records. For more information, see <i>Siebel Data Quality Administration Guide</i> .
Database Extract	DbXtract	Batch	No	Extracts visible data for a Siebel Remote client. For more information, see <i>Siebel Remote and Replication Manager Administration Guide</i> .
Document Server	DocServer	Batch	Yes	Generates documents. For more information, see <i>Siebel Applications Administration Guide</i> .
EAI Object Manager	EAIObjMgr	Interactive	Yes	Siebel EAI Object Manager. For more information, see <i>Overview: Siebel Enterprise Application Integration</i> .
eCG Sales Mobile Object Manager	CGMObjMgr	Interactive	Yes	eCG Sales Mobile Object Manager. For more information, see Siebel Mobile applications documentation on <i>Siebel Bookshelf</i> .
eChannel Object Manager	eChannelObjMgr	Interactive	Yes	Siebel eChannel Object Manager. For more information, see <i>Siebel Partner Relationship Management Administration Guide</i> .
eCustomer Object Manager	eCustomerObjMgr	Interactive	Yes	Siebel eCustomer Object Manager. For more information, see <i>Siebel Self Service Administration Guide</i> .
eEvents Object Manager	eEventsObjMgr	Interactive	Yes	Siebel eEvents Object Manager. For more information, see <i>Siebel Events Management Guide</i> .
Email Manager	MailMgr	Background	No	Sends individual email messages. For more information, see <i>Siebel Business Process Framework: Workflow Guide</i> .
eMarketing Object Manager	eMarketObjMgr	Interactive	Yes	Siebel eMarketing Object Manager. For more information, see <i>Siebel Marketing Installation and Administration Guide</i> .
Enterprise Integration Mgr	EIM	Batch	No	Integrates enterprise data to and from other systems. For this component to run, the Server Request Processor component must also be running. For more information, see <i>Siebel Enterprise Integration Manager Administration Guide</i> .
ePharma Mobile Object Manager	ePharmaMObjMgr	Interactive	Yes	ePharma Mobile Object Manager. For more information, see Siebel Mobile applications documentation on <i>Siebel Bookshelf</i> .

Table A–2 (Cont.) Predefined Siebel Server Components

Component Name	Alias	Mode	Multi-threaded	Description
eSales Object Manager	eSalesObjMgr	Interactive	Yes	Siebel eSales Object Manager. For more information, see <i>Siebel eSales Administration Guide</i> .
Field Service Cycle Counting Engine	FSCyccnt	Batch	Yes	Field Service Cycle Counting Engine. For this component to run, the Server Request Processor component must also be running. For more information, see <i>Siebel Field Service Guide</i> .
Field Service Mobile Inventory Transaction Engine	FSInvTxn	Batch	Yes	Field Service Mobile Inventory Transaction Engine. For this component to run, the Server Request Processor component must also be running. For more information, see <i>Siebel Field Service Guide</i> .
Field Service Object Manager	SFSObjMgr	Interactive	Yes	Siebel Field Service Object Manager. For this component to run, the Server Request Processor component must also be running. For more information, see <i>Siebel Field Service Guide</i> .
Field Service Replenishment Engine	FSRepl	Batch	Yes	Replenishes inventory locations. For this component to run, the Server Request Processor component must also be running. For more information, see <i>Siebel Field Service Guide</i> .
File System Manager	FSMSrvr	Batch	Yes	Manages the Siebel File System. For more information, see " Administering the Siebel File System " on page 8-5.
FINS Mobile Object Manager	FINSMObjMgr	Interactive	Yes	FINS Mobile Object Manager. For more information, see Siebel Mobile applications documentation on <i>Siebel Bookshelf</i> .
Forecast Service Manager	FcstSvcMgr	Batch	Yes	Executes forecast operations. For more information, see <i>Siebel Forecasting Guide</i> .
Generate New Database	GenNewDb	Batch	No	Generates a new Oracle Database XE database template file for Siebel Remote. For more information, see <i>Siebel Remote and Replication Manager Administration Guide</i> .
Generate Triggers	GenTrig	Batch	No	Generates triggers for Workflow Manager and Assignment Manager. For more information, see <i>Siebel Business Process Framework: Workflow Guide</i> .
JMS Receiver	JMSReceiver	Background	No	Preconfigured receiver for inbound JMS messages. For more information, see <i>Overview: Siebel Enterprise Application Integration</i> .
List Import Service Manager	ListImportSvcMgr	Batch	Yes	Loads lists of data into the Siebel database. For this component to run, the Server Request Processor component must also be running. For more information, see <i>Siebel Marketing Installation and Administration Guide</i> .

Table A–2 (Cont.) Predefined Siebel Server Components

Component Name	Alias	Mode	Multi-threaded	Description
Marketing Object Manager	SObjMgr	Interactive	Yes	Siebel Marketing Object Manager. For more information, see <i>Siebel Marketing Installation and Administration Guide</i> .
Major Alignment - Territory Rules Merge Manager	MajTerrMergeMgr	Batch	Yes	Merges staging rules with production rules for major alignment. For more information, see <i>Siebel Territory Management Guide</i> .
Minor Alignment - Territory Rules Merge Manager	MinTerrMergeMgr	Batch	Yes	Merges staging rules with production rules for minor alignment. For more information, see <i>Siebel Territory Management Guide</i> .
Mobile Data Extraction	MobileDbXtract	Batch	No	Extracts visible data for a Siebel Mobile disconnected client. For more information, see <i>Siebel Mobile Guide: Disconnected</i> .
MQSeries AMI Receiver	MqSeriesAMIRcvr	Background	No	Preconfigured receiver for inbound MQSeries AMI messages. For more information, see <i>Transports and Interfaces: Siebel Enterprise Application Integration</i> .
MQSeries Server Receiver	MqSeriesSrvRcvr	Background	No	Preconfigured receiver for inbound MQSeries server messages. For more information, see <i>Transports and Interfaces: Siebel Enterprise Application Integration</i> .
MSMQ Receiver	MSMQRcvr	Background	No	Preconfigured receiver for inbound MSMQ server messages. For more information, see <i>Transports and Interfaces: Siebel Enterprise Application Integration</i> .
Optimization Engine	Optimizer	Batch	Yes	Optimizes vehicle routing. For more information, see <i>Siebel Field Service Guide</i> .
Page Manager	PageMgr	Background	No	Sends pages generated by the Workflow Manager. For more information, see <i>Siebel Business Process Framework: Workflow Guide</i> .
Parallel Database Extract	PDbXtract	Batch	No	Extracts visible data for a Siebel Mobile disconnected client or for a Siebel Remote or Replication Manager client. For more information, see <i>Siebel Mobile Guide: Disconnected</i> or <i>Siebel Remote and Replication Manager Administration Guide</i> .
Partner Manager Object Manager	PManagerObjMgr	Interactive	Yes	Siebel Partner Manager Object Manager. For more information, see <i>Siebel Partner Relationship Management Administration Guide</i> .
Siebel Partner Portal Object Manager	PartnerPortalObjMgr	Interactive	Yes	Siebel Partner Portal Object Manager. For more information, see <i>Siebel Partner Relationship Management Administration Guide</i> .
PIMSI Engine	PIMSIEng	Batch	Yes	Executes real-time business processes. For more information, see <i>Siebel Server Sync Guide</i> .

Table A–2 (Cont.) Predefined Siebel Server Components

Component Name	Alias	Mode	Multi-threaded	Description
PIMSI Dispatcher	PIMSIDispatcher	Batch	Yes	Executes real-time business processes. For more information, see <i>Siebel Server Sync Guide</i> .
Preventive Maintenance Engine	FSPrevMnt	Batch	Yes	Generates service requests and activities for preventive maintenance. For more information, see <i>Siebel Field Service Guide</i> .
Replication Agent	RepAgent	Background	No	Synchronizes a regional database with a parent database. For more information, see <i>Siebel Remote and Replication Manager Administration Guide</i> .
RTI Batch	RTIBatch	Batch	No	Executes SQL statements in a batch. For more information, see <i>Siebel Territory Management Guide</i> .
Sales Hierarchy Service Manager	SalesHierSvcMgr	Batch	Yes	Batch executes sales hierarchy service operations.
Sales Mobile Object Manager	SalesmObjMgr	Interactive	Yes	Siebel Sales Mobile Object Manager. For more information, see Siebel Mobile applications documentation on <i>Siebel Bookshelf</i> .
Sales Object Manager	SSEObjMgr	Interactive	Yes	Siebel Sales Object Manager.
Search Data Processor	SearchDataProcessor	Batch	Yes	Processes search data and builds indexes. For more information, see <i>Siebel Search Administration Guide</i> .
Search Incremental Index Processor	SearchIncrementalIndexProcessor	Batch	Yes	Processes search data and builds an index incrementally. For more information, see <i>Siebel Search Administration Guide</i> .
Self Service Object Manager	SServiceObjMgr	Interactive	Yes	Siebel Self Service Object Manager. For more information, see <i>Siebel Self Service Administration Guide</i> .
Server Manager	ServerMgr	Interactive	No	Administers configuration data within the Siebel Enterprise Server. For more information, see " About Siebel Server Manager " on page 2-5.
Server Request Broker	SRBroker	Interactive	Yes	Routes requests and asynchronous notifications among clients and components. For more information, see " About Server Request Broker (SRBroker) " on page 8-1.
Server Request Processor	SRProc	Background	Yes	Server request scheduler and request or notification store-and-forward processor. For more information, see " About Server Request Processor (SRProc) " on page 8-2.
Server Tables Cleanup	SvrTblCleanup	Background	No	Deletes completed and expired server request records. For more information, see " About Server Tables Cleanup (SvrTblCleanup) " on page 8-4.
Server Task Persistence	SvrTaskPersist	Background	No	Persists all of the tasks created by the Siebel Server.

Table A–2 (Cont.) Predefined Siebel Server Components

Component Name	Alias	Mode	Multi-threaded	Description
Service Mobile Object Manager	ServicemObjMgr	Interactive	Yes	Siebel Service Mobile Object Manager. For more information, see Siebel Mobile applications documentation on <i>Siebel Bookshelf</i> .
Service Order Fulfillment Engine	FSFulfill	Batch	Yes	Fulfills pending service orders. For more information, see <i>Siebel Field Service Guide</i> .
Service Order Part Locator Engine	FSLocate	Batch	Yes	Locates pending service orders. For more information, see <i>Siebel Field Service Guide</i> .
Siebel Administrator Notification Component	AdminNotify	Batch	Yes	Administers the server component notification feature. For more information, see " About System Alert Notification " on page 4-14.
Siebel Connection Broker	SCBroker	Background	No	Brokers inbound connection requests for interactive-mode server components (Application Object Managers) and load-balances session requests between multiple instances of interactive-mode server components. For more information, see " About Siebel Connection Broker (SCBroker) " on page 8-3.
Siebel Product Configuration Object Manager	eProdCfgObjMgr	Interactive	Yes	Configuration server for complex products. For more information, see <i>Siebel Product Administration Guide</i> .
Siebel Server	SiebSrvr	Background	No	Siebel Server root process and network listener.
Siebel Server Scheduler	SrvrSched	Background	No	Supports the running of Siebel Server and server components by spawning component processes as requested by the Siebel Server. For more information, see " About Siebel Server Scheduler (SrvrSched) " on page 8-4.
Siebel Web Tools Object Manager	SWToolsObjMgr	Interactive	Yes	Siebel Web Tools Object Manager. For more information, see <i>Using Siebel Tools</i> .
Smart Answer Manager	SmartAnswer	Batch	No	Categorizes text in email messages. For more information, see <i>Siebel Smart Answer Guide</i> .
Synchronization Manager	SynchMgr	Interactive	Yes	Manages Siebel Remote and Replication Manager synchronization sessions. For more information, see <i>Siebel Remote and Replication Manager Administration Guide</i> .
Task Log Cleanup	TaskLogCleanup	Background	No	Cleans up the task transaction storage after transactions are committed. For more information, see <i>Siebel Business Process Framework: Task UI Guide</i> .
Transaction Merger	TxnMerge	Background	No	Merges transactions from Siebel Remote and Replication Manager clients into the Siebel database. For more information, see <i>Siebel Remote and Replication Manager Administration Guide</i> .

Table A–2 (Cont.) Predefined Siebel Server Components

Component Name	Alias	Mode	Multi-threaded	Description
Transaction Processor	TxnProc	Background	No	Prepares the transaction log for the Transaction Router. For more information, see <i>Siebel Mobile Guide: Disconnected</i> or <i>Siebel Remote and Replication Manager Administration Guide</i> .
Transaction Router	TxnRoute	Background	No	Routes visible transactions to Siebel Mobile disconnected clients or to Siebel Remote or Replication Manager clients. For more information, see <i>Siebel Mobile Guide: Disconnected</i> or <i>Siebel Remote and Replication Manager Administration Guide</i> .
Upgrade Kit Builder	UpgKitBldr	Batch	Yes	Creates the upgrade kit based on information collected by the Upgrade Kit Wizard. For more information, see <i>Siebel Anywhere Administration Guide</i> .
Workflow Action Agent	WorkActn	Background	No	Executes Workflow Manager actions. For more information, see <i>Siebel Business Process Framework: Workflow Guide</i> .
Workflow Monitor Agent	WorkMon	Background	No	Monitors Workflow Manager events. For more information, see <i>Siebel Business Process Framework: Workflow Guide</i> .
Workflow Process Batch Manager	WfProcBatchMgr	Batch	Yes	Executes workflow processes in a batch. For more information, see <i>Siebel Business Process Framework: Workflow Guide</i> .
Workflow Process Manager	WfProcMgr	Batch	Yes	Executes real-time workflow processes. For more information, see <i>Siebel Business Process Framework: Workflow Guide</i> .
Workflow Recovery Manager	WfRecvMgr	Batch	Yes	Recovers interrupted workflow processes due to Siebel Server failures. For more information, see <i>Siebel Business Process Framework: Workflow Guide</i> .

Siebel Enterprise, Server, and Component Parameters

[Table A–3](#) lists some of the Siebel Enterprise Server, Siebel Server, and generic component parameters and their related attributes. More complete descriptions of each listed parameter follow this table. In most cases, the parameters with *** shown as the default value are initially set during the initial configuration tasks (based on the input specified by the administrator). For the parameters with +++ shown as the default value, the actual default values differ from component to component. Review the documentation pertinent to the individual component for more information.

Note: Not all of the parameters used by Siebel Business Applications are described in this book. Many parameters are primarily described elsewhere on *Siebel Bookshelf*, while some parameters are not documented on *Siebel Bookshelf*.

Table A-3 Parameters and Attributes

Parameter Name	Alias	Level	Req	Override	Effective Immed	Dynamic	Default Value
Enterprise Server Description	EnterpriseDesc	Enterprise	No	No	No	No	***
Indexspace Name	IdxSpace	Enterprise	No	Yes	Yes	Yes	***
ODBC Data Source	Connect	Enterprise	Yes	Yes	Yes	No	***
Siebel File System	FileSystem	Enterprise	Yes	Yes	Yes	No	***
Siebel Repository	Repository	Enterprise	No	Yes	No	No	Siebel Repository
Table Owner	TableOwner	Enterprise	No	No	No	No	***
Table Owner Password	TableOwnPass	Enterprise	No	No	No	Yes	***
Tablespace Name	TblSpace	Enterprise	No	No	No	No	***
Upgrade Component	UpgradeComponent	Enterprise	No	No	Yes	No	Siebel HQ Server
Auto Startup Mode	AutoStart	Server	No	No	Yes	No	True
Communication Transport	Comm	Server	Yes	No	Yes	No	TCPIP
Compression Type	Compress	Server	No	No	Yes	No	NONE
Component Priority Level Timeout	CompPriorityTime	Server	No	No	No	No	Not applicable
Encryption Type	Crypt	Server	No	No	Yes	No	NONE
Host Name	Host	Server	Yes	No	No	No	***
Log Archive Keep	LogArchive	Server	No	No	Yes	No	10
Log Segment Size	LogSegmentSize	Server	No	No	No	No	Not applicable
Log Maximum Segments	LogMaxSegments	Server	No	No	No	No	Not applicable
Server Description	ServerDesc	Server	No	No	No	No	***
Server Shutdown Wait Time	ShutdownTime	Server	No	No	Yes	Yes	60
Siebel Root Directory	RootDir	Server	Yes	No	No	No	***
Siebel Server Name	Server	Server	Yes	No	Yes	No	***
Size of Error Buffer	ErrorBufferSize	Server	No	No	No	No	1000
Synchronization Port	SyncPort	Server	Yes	No	Yes	No	40400
Alert Level	AlertLevel	Generic	No	Yes	Yes	Yes	1
Application Datasource	CFGDatasource	Generic	No	Not applicable	Yes	No	ServerDataSrc

Table A-3 (Cont.) Parameters and Attributes

Parameter Name	Alias	Level	Req	Override	Effective Immed	Dynamic	Default Value
Application Scripting Enabled	CFGEnableScripting	Generic	No	Not applicable	Yes	No	True
Application Shared Mode users directory	CFGSharedModeUsersDir	Generic	No	Not applicable	Yes	No	Not applicable
Auto Restart	AutoRestart	Generic	No	No	No	No	False
Compressed File Download	CompressedFileDownload	Generic	No	No	No	No	True
DB Multiplex - Max Number of Shared DB Connections	MaxSharedDbConns	Generic	No	Not applicable	No	No	-1
DB Multiplex - Min Number of Dedicated DB Connections	MinTrxDBConns	Generic	No	Not applicable	No	No	-1
DB Multiplex - Min Number of Shared DB Connections	MinSharedDbConns	Generic	No	Not applicable	No	No	-1
Default Tasks	DfltTasks	Generic	Yes	No	No	No	0
Error Flags	ErrorFlags	Generic	No	Yes	Yes	Yes	0
Honor MaxTasks	HonorMaxTasks	Generic	No	No	No	No	False
Language Code	Lang	Generic	Yes	Yes	Yes	No	ENU
Locale Code	LocaleCode	Generic	Yes	Yes	Yes	No	***
Local load balancing upper threshold	UpperThreshold	Generic	No	Yes	No	No	100
Log Print Timestamp	LogTimestamp	Generic	No	Yes	Yes	Yes	False
Maximum depth of the query	MaxDepthOfTheQuery	Generic	No	No	No	No	500
Maximum MT Servers	MaxMTServers	Generic	Yes	No	No	No	1
Maximum Processes	MaxProcs	Generic	Yes	Yes	No	No	20
Maximum Tasks	MaxTasks	Generic	Yes	No	No	No	+++
Memory Usage Based Multithread Shell Recycling	MemoryBasedRecycle	Generic	No	Yes	No	No	False
Minimum MT Servers	MinMTServers	Generic	Yes	No	No	No	1
Minimum Up Time	MinUpTime	Generic	No	No	No	No	60
Multithreaded	Threaded	Generic	Yes	No	No	No	False

Table A-3 (Cont.) Parameters and Attributes

Parameter Name	Alias	Level	Req	Override	Effective Immed	Dynamic	Default Value
Number of lines after which to flush the log file	LogFlushFreq	Generic	No	No	Yes	No	0
Number of Restarts	NumRestart	Generic	No	No	No	No	10
Number of Retries	NumRetries	Generic	No	No	No	No	10000
Number of Sessions per SISNAPI Connection	SessPerSisnConn	Generic	No	Not applicable	No	No	20
OM - Data Source	DataSource	Generic	No	Not applicable	Yes	No	ServerDataSrc
OM - Named Data Source name	NamedDataSource	Generic	No	Not applicable	Yes	No	ServerDataSrc, GatewayData Src
OM - Model Cache Maximum	ModelCacheMax	Generic	No	Not applicable	Yes	No	10
OM - Preload SRF Data	PreloadSRF	Generic	No	Not applicable	No	No	False
OM - Resource Language Code	ResourceLanguage	Generic	No	Not applicable	Yes	No	Not applicable
OM - Save Preferences	SavePreferences	Generic	No	Yes	No	No	True
Password	Password	Generic	Yes	Yes	Yes	Yes	***
Process VM Usage Lower Limit	MemoryLimit	Generic	No	Yes	No	No	1500
Process VM Usage Upper Limit	MemoryLimitPercent	Generic	No	Yes	No	No	20
Retry Interval	RetryInterval	Generic	No	No	No	No	5
Retry Up Time	RetryUpTime	Generic	No	No	No	No	600
Session Keepalive Timeout	SessKeepAlive	Generic	No	Yes	No	No	7200
SISNAPI Connection Maximum Idle Time	ConnIdleTime	Generic	No	Yes	Yes	No	-1
SISNAPI - Log Traffic	LogTraffic	Generic	No	Not applicable	Yes	Yes	False
Sleep Time	SleepTime	Generic	No	Yes	Yes	Yes	60
SQL Trace Flags	SQLFlags	Generic	No	Yes	Yes	Yes	0
Static Port Number	PortNumber	Generic	Yes	No	Yes	No	0
Trace Flags	TraceFlags	Generic	No	Yes	Yes	Yes	0

Table A-3 (Cont.) Parameters and Attributes

Parameter Name	Alias	Level	Req	Override	Effective		Default Value
					Immed	Dynamic	
Use IP Address	UseIPAddress	Generic	No	No	No	No	True
Use Shared Log File	LogUseSharedFile	Generic	No	Not applicable	No	No	False
User Name	Username	Generic	Yes	Yes	Yes	Yes	***

Siebel Enterprise Server Parameters

This topic describes in detail the Siebel Enterprise Server parameters listed in [Table A-3](#).

Enterprise Server Description (alias EnterpriseDesc). A description of the Siebel Enterprise Server, used for identification in Server Manager views. The system prompts you for the value of this parameter during the configuration of the Siebel Enterprise Server after installation.

Indexspace Name (alias IdxSpace). The indexspace name for the Siebel database schema tables. This parameter specifies the name of the storage space in which to create the indexes for the Siebel database schema. The exact physical meaning of this parameter is database platform-specific. To determine whether this parameter applies to your database platform, see the *Siebel Installation Guide* for the operating system you are using.

ODBC Data Source (alias Connect). The ODBC data source name for the Siebel database schema connectivity. The default data source is created during the initial configuration of the Siebel Server, but can be overridden for a component or task. This data source must be created as a system DSN. Note that this parameter is case-sensitive.

Siebel File System (alias FileSystem). The Siebel File System path names. The specification of the File System paths must be valid relative to the computer on which the Siebel Server is installed. The value of the parameter cannot exceed 2048 characters. Multiple File System directories can be specified for this parameter by using commas to delimit each directory. For example, the following value specifies two directories hosted on different server computers:

```
\\server_name1\fs\, \\server_name2\fs\
```

Siebel Repository (alias Repository). The name of the Siebel Repository for application configuration information. The default value is Siebel Repository. There can only be one active repository for each database.

Table Owner (alias TableOwner). The table owner for the Siebel database schema:

- For Oracle Database, you are prompted for the default value for Table Owner during the Siebel Server initial configuration.
- For Microsoft SQL Server, the value defaults to dbo.

Table Owner Password (alias TableOwnPass). The database password for the table owner account. This value must be set in order to run Siebel Server components that manipulate objects in the Siebel database schema.

Tablespace Name (alias TblSpace). The tablespace name for the Siebel database schema tables. This parameter specifies the name of the storage space in which to create the tables for the Siebel database schema. The exact physical meaning of this parameter is database platform-specific. To determine whether this parameter applies

to your database platform, see the *Siebel Installation Guide* for the operating system you are using.

Upgrade Component (alias UpgradeComponent). Used by Siebel Anywhere to determine which Siebel Anywhere configuration is version-checked. By default, the value is Siebel HQ Server. On a regional Siebel Server, change this value to Siebel Regional Server.

Siebel Server Parameters

This topic describes in detail the Siebel Server parameters listed in [Table A-3](#).

Auto Startup Mode (alias AutoStart). Indicates whether the Siebel Server components start automatically on Siebel Server startup. This parameter defaults to True, which indicates that the Siebel Server components are fully enabled and the default number of Siebel Server processes start when the Siebel Server system service starts (or the computer restarts). If Auto Startup Mode is set to False, then the Siebel Server components enter a shutdown state after the Siebel Server system service starts.

Communication Transport (alias Comm). The name of the transport type for network communications, for example, TCPIP.

Component Priority Level Timeout (alias CompPriorityTime). The amount of time to wait before starting lower-priority components. Components are prioritized as follows:

- Components in the System Management component group have the highest priority. These components start first.
- Components in the Auxiliary System Management component group start next.
- Components in the remaining component groups have the lowest priority.

The Siebel Server starts components in the System Management component group and waits for the maximum number of seconds, specified by the Component Priority Level Timeout parameter, for these components to initialize. If, at the expiry of Component Priority Level Timeout, the components fail to initialize, then the Siebel Server attempts to start the components in the Auxiliary System Management component group. If the components in this component group fail to initialize before the expiry of Component Priority Level Timeout, then the Siebel Server attempts to start the lowest priority components.

Note: The Siebel Server attempts to start lower-level components irrespective of the dependencies of these components in the Auxiliary System Management component group, such as File System Manager or Server Request Processor.

Compression Type (alias Compress). The type of compression (NONE or ZLIB) for network communications sent internally between the Application Object Manager and the Siebel Application Interface. See also the information about configuring Siebel Application Interface profiles using Siebel Management Console and about the setting HTTP 1.1-Compliant Firewall / Enable Web Compression, in the *Siebel Installation Guide* for the operating system you are using.

Encryption Type (alias Crypt). The type of encryption (NONE or RSA) for network communications between Siebel Application Interface and the Application Object Manager. See also the information about configuring Siebel Server profiles using Siebel Management Console and about the setting Security Encryption Level or Type, in the *Siebel Installation Guide* for the operating system you are using. If you are using Siebel

Remote, then you must use RSA. For more information about encryption, see *Siebel Security Guide*.

Host Name (alias Host). The name of the host computer on which the Siebel Server is installed. The value is set automatically during the initial configuration of the Siebel Server, but can be changed if you want to route connection requests through a network card bound to a different host name.

Log Archive Keep (alias LogArchive). The number of log archive directories to keep in the `logarchive` directory. Each time the Siebel Server system service starts, the current `log` subdirectory moves to the `logarchive` subdirectory, tagged with the incarnation number of the Siebel Server. This parameter indicates the number of previous `logarchive` directories to retain. If this parameter is set to 0, then the current `log` subdirectory is not archived upon startup of the Siebel Server system service. If this parameter is set to -1, then the Siebel Server keeps `logarchive` subdirectories. After moving the `log` directory, a new `log` directory is created, inheriting the permissions from the parent `siebsrvr` directory.

Log Segment Size (alias LogSegmentSize). Determines how large a segment of the log file is, in 512 byte blocks. For example, if you set this parameter to 10, then the log segment will be 5 KB in size. A value of 0 turns off segmentation.

Log Maximum Segments (alias LogMaxSegments). Determines the number of log segments that are kept. If you set this parameter to 1, then only one segment is kept. When this segment reaches the size specified by the Log Segment Size parameter, the segment is overwritten. In general, set this parameter to a high value, such as 20. In this case, the twenty-first segment overwrites the first segment, and so forth.

Server Description (alias ServerDesc). A description of the Siebel Server, used for identification in Siebel Server Manager views. The value of this parameter is prompted for during the initial configuration of the Siebel Server.

Server Shutdown Wait Time (alias ShutdownTime). The time to wait (in seconds) during a Siebel Server shutdown before killing component processes. When a Siebel Server is shut down (either from the Siebel Server Manager, when the Siebel Server system service is stopped, or when the computer is shut down or restarted), the currently running component tasks are notified. If the tasks do not shut down within the time specified by the Server Shutdown Wait Time parameter, then the Siebel Server kills the component processes directly and then finishes shutting down. The default value of this parameter is 60 seconds.

Siebel Root Directory (alias RootDir). The root installation directory for the Siebel Server. Every Siebel Server subdirectory is directly under this directory (such as `admin`, `dbtempl`, `docking`, `log`, `logarchive`, `upgrade`, and so on). Do not change the value for this parameter.

Siebel Server Name (alias Server). The name of the Siebel Server. This parameter is specified during the initial configuration of the Siebel Server. The name of the Siebel Server cannot be changed after it is initially configured. The Siebel Server Name parameter can contain only alpha characters, numerals, underscores, or a combination thereof. Parameter names must also lead with an alpha character and can be no longer than 12 characters. For more information about the name of the Siebel Server, see the *Siebel Installation Guide* for the operating system you are using.

Size of Error Buffer (alias ErrorBufferSize). The number of entries in the shared memory circular error buffer used by the Siebel Server. This buffer receives all level 0 and level 1 error messages.

Synchronization Port (alias SyncPort). The TCP/IP port number for the Synchronization Server component. The Mobile Web Clients that synchronize with this

Siebel Server must be configured to connect to this port when initiating a synchronization session (in the `DockConnString` parameter of the client configuration file).

Generic Parameters

This topic describes in detail some of the generic parameters listed in [Table A-3](#). Many of these parameters can be set at the Siebel Enterprise Server, Siebel Server, or component levels.

Alert Level (alias `AlertLevel`). The level of logging to the Server Alert File. The value is set to 1 by default, but more detailed information can be specified by setting the parameter to a higher value. Currently, only levels 1 and 2 are supported. Level 1 sends only information about abnormal process and task terminations to the Alert File. Level 2 sends information about every process or task when it exits, whether normally or unexpectedly.

Application Datasource (alias `CFGDatasource`). The Application Object Manager default configuration data source. The value for this parameter is one of the values listed for the OM - Named Data Source name parameter.

Application Scripting Enabled (alias `CFGEnableScripting`). Determines whether the Application Object Manager server component can execute a server script. If you set this to True, then scripting DLL files are loaded and the application can then execute scripts. The default value for this parameter is True. Setting this parameter to False also disables browser scripts in addition to server scripts.

Application Shared Mode users directory (alias `CFGSharedModeUsersDir`). Specifies the users directory used in shared mode. Update the value of this parameter if you change the location of the Siebel File System.

Application * Font. Several parameters with names starting with *Application* and ending in *Font* specify fonts to use for Siebel application user interface elements unless these settings are overridden by font specifications in style sheets (CSS).

Auto Restart (alias `AutoRestart`). Indicates whether this component can be restarted automatically. This parameter works in conjunction with the Number of Restarts parameter to determine the number of attempts that are made to restart the target component.

Note: For multithreaded server components, auto-restart does not occur if a process initially fails to start and is terminated by the Siebel application. Only processes that reach the running state are restarted.

Compressed File Download (alias `CompressedFileDownload`). By default, files are downloaded to a client's browser in a compressed form when using Siebel File System Manager. On certain versions of Microsoft Internet Explorer, this operation might result in the renaming of the file. If you want to disable compressed file download, then set this parameter to False for the Application Object Manager for which you want this feature to be disabled. The default value is True.

DB Multiplex - Max Number of Shared DB Connections (alias `MaxSharedDbConns`). One of two parameters that configure shared database connections. (The other parameter is DB Multiplex - Min Number of Shared DB Connections.) Shared connections are used by most Application Object Manager operations. DB Multiplex - Max Number of Shared DB Connections controls the maximum number of shared database connections, and is defined for each component. That is, DB Multiplex - Max Number of Shared DB Connections controls the maximum

total number of shared database connections for the component on each Siebel Server, not an instance (task or process) of the component. A setting of -1 disables this parameter and is the default setting.

DB Multiplex - Min Number of Dedicated DB Connections (alias MinTrxDBConns).

Controls the minimum number of dedicated database connections within an Application Object Manager process. Dedicated database connections are used primarily by specialized Siebel components, such as Siebel EAI, that need transactions to span multiple Application Object Manager operations. The DB Multiplex - Min Number of Dedicated DB Connections parameter is defined for each instance of the component. That is, DB Multiplex - Min Number of Dedicated DB Connections controls the minimum number of dedicated database connections for each instance (process) of the component, not for the entire component. This functionality is different from the parameters that configure shared database connections. A setting of -1 disables this parameter and is the default setting.

DB Multiplex - Min Number of Shared DB Connections (alias

MinSharedDBConns). One of two parameters that configure shared database connections. (The other parameter is DB Multiplex - Max Number of Shared DB Connections.) Shared connections are used by most Application Object Manager operations. DB Multiplex - Min Number of Shared DB Connections controls the minimum number of shared database connections, and is defined for each component. That is, DB Multiplex - Min Number of Shared DB Connections controls the minimum number of shared database connections a component tries to maintain on each Siebel Server across all instances of this component. A setting of -1 disables this parameter and is the default setting.

Note: Set the DB Multiplex - Min Number of Shared DB Connections parameter less than the value of the Maximum Tasks (alias MaxTasks) parameter. Setting this value greater than MaxTasks disables database connection pooling.

Default Tasks (alias DfltTasks). The number of processes to start for a background mode component when the component is started explicitly through the Siebel Server Manager, or when the Siebel Server is started (if the component state was last set to Running). Components with a Default Tasks parameter set to a value greater than zero start automatically when the Siebel Server is started.

EnabledTC (alias EnabledTC). When set to True for an Application Object Manager, enables a terms and conditions page that users must accept to be allowed into the Siebel application. Additional configuration steps apply, which are described on My Oracle Support in article 478253.1 (Article ID).

Error Flags (alias ErrorFlags). Specifies the flags used for tracing error information. This parameter is used to turn on various types of component-specific error tracing.

Export Status Size (alias ExportStatusSize). Specifies the number of records to be exported in an export operation performed by the Application Object Manager component.

Honor MaxTasks (alias HonorMaxTasks). When the parameter value is True, a component process that reaches Max Tasks stops accepting requests from the Server Request Broker. If another request is sent, then an error message results. The process resumes accepting requests after some tasks finish. If the parameter value is False, then all of the requests are queued in the component process.

Language Code (alias Lang). The three-letter language code for the component processes. Translatable messages (including error messages) are output in the specified language. The translated message files for the language must exist in the locale subdirectory of the Siebel Server installation. For more information, see *Siebel Global Deployment Guide*.

Locale Code (alias LocaleCode). The three-letter locale code for the component processes. A locale is a set of rules guiding how common data is displayed to the user or is received from the user. Siebel Business Applications support formatting of data, such as dates, time, numbers, and currency, based on locale settings. Locales are administered using the Locale view in the Administration - Data screen. For more information, see *Siebel Global Deployment Guide*.

Note: Siebel Business Applications use the three-letter code conventions of Microsoft for locale and language code. For more information about setting locales, see *Siebel Applications Administration Guide*.

Local load balancing upper threshold (alias UpperThreshold). Determines the load threshold at which a new Application Object Manager process starts, and is based on the load percentage of a given Application Object Manager process. For example, setting this parameter to 80 percent on an Application Object Manager that handles 50 concurrent sessions starts a new Application Object Manager process when 40 sessions become active. The default value is 100 percent. For more information about load balancing, see *Siebel Deployment Planning Guide*.

Note: If the Application Object Manager parameter Minimum MT Servers is equal to Maximum MT Servers, then the effective value for this parameter is 100 percent, despite the actual setting.

Log Print Timestamp (alias LogTimestamp). Specifies whether to print a timestamp on records written to the trace files. The value is set to True by default, but administrators might want to override it to False for components that perform a large amount of logging (or if a high value is set for the Trace Flags or SQL Trace Flags parameters).

Maximum depth of the query (alias MaxDepthOfTheQuery). Allows you to increase the maximum parse depth of a query with a large search specification, including, for example, a large number of OR or AND clauses.

You might receive this error: The query could not be run because it is too big. If you receive errors indicating that a query cannot run because it is too big, then you might refine the query to be more selective or to use parentheses. Alternatively, you can try setting this parameter to a larger value to eliminate the error. The default value is 500.

If you need to adjust this parameter value, then the setting you choose must correlate to the default stack size for your server operating system. For example, a value of 800 will generally work on Microsoft Windows, for which the default stack size is 1 MB, while a value of 500 will generally work on Linux or UNIX operating systems, for which the default stack size is 512 KB. If you increase the stack size for your operating system, then you can use a higher setting for this parameter.

You can optionally set this parameter at the enterprise level or the server level. You can also set MaxDepthOfTheQuery in the application configuration file for the Siebel

Mobile Web Client or Developer Web Client (in the [InfraObjMgr] section), or set it in the tools.cfg file for Siebel Tools.

Caution: Changing the operating system stack size can adversely impact the computer or application performance and should not be attempted without due diligence and consultation with experts.

Maximum MT Servers (alias MaxMTServers). Specifies the maximum number of multithreaded Siebel Server processes to be run concurrently for a component that has multithreading enabled. Note that only batch mode and interactive mode components can run with multithreaded set to True. Tasks and client sessions run as threads within the multithreaded Siebel Server processes.

The number of tasks that can run in each Siebel Server process is determined by the value of the Maximum Tasks parameter divided by Maximum MT Servers. Increase or decrease the value of Maximum MT Servers based on the number of users for the given component process. For more information about this parameter, see *Siebel Performance Tuning Guide*.

Maximum Processes (alias MaxProcs). Specifies the maximum number of concurrent running processes for a Siebel Server component. The Siebel Server must be restarted in order for any changes to this parameter to take effect.

Maximum Tasks (alias MaxTasks). Specifies the maximum number of background mode, batch mode, or interactive mode processes or threads that can run concurrently for a component. This value applies to threads for components that have multithreading enabled, or otherwise component processes. Increase or decrease this value based on the number of users for the given component process. This value also determines the number of tasks for each component that are tracked by the Siebel Server. For more information about this parameter, see *Siebel Performance Tuning Guide*.

Note: Multithreaded Siebel Server processes are not included in the counting of tasks. The tasks run as threads within the processes. These multithreaded processes are guided by the Minimum MT Servers and Maximum MT Servers parameters.

Memory Usage Based Multithread Shell Recycling (alias MemoryBasedRecycle). If it is set to True, then processes for this component are recycled automatically when virtual memory usage reaches a specified threshold. The threshold is set using the parameter Process VM Usage Lower Limit. For example, when a component is set with this parameter and the memory usage has exceeded the configured threshold, the recycling procedure begins by disabling new tasks, spawning a new process, and commencing a normal shutdown (that is, waiting for all of the tasks to finish before shutting down). The default value is False. Use this parameter to remedy your application only if excessive memory usage created by memory leaks seems to be occurring.

Minimum MT Servers (alias MinMTServers). Specifies the default number of multithreaded Siebel Server processes that are started for a component that has multithreading enabled. These processes are brought up when the component is started explicitly through the Siebel Server Manager, or when the Siebel Server is started (if the component state was last set to Running).

Additional multithreaded Siebel Server processes are started as needed (namely, when the maximum number of threads that can run in a Siebel Server process has been

reached), up to the value of the Maximum MT Servers parameter. Setting this parameter to 0 disables the component. For more information about this parameter, see *Siebel Performance Tuning Guide*.

Minimum Up Time (alias MinUpTime). Specifies the minimum time that a multithreaded server component such as an Application Object Manager must be up for a restart to be successful (in seconds). In order for the component restart to be considered successful, the component must be running for the duration specified by this parameter. This parameter works with the Number of Restarts parameter to determine the number of restart attempts in a time interval allowed for a component (NumRestart multiplied by MinUpTime). If a component instance cannot be restarted after this time interval, then no new restart is attempted (the component instance will not be running). The default value for this parameter is 60 seconds.

Multithreaded (alias Threaded). Specifies whether the component is multithreaded or multiprocess. This parameter only applies to batch-mode and interactive-mode components. Use the default value for this parameter.

Caution: Do not change the value of this parameter without direct guidance Global Customer Support. For help with changing the value of this parameter, create a service request (SR) on My Oracle Support. Alternatively, you can phone Global Customer Support directly to create a service request or get a status update on your current SR. Support phone numbers are listed on My Oracle Support.

Number of lines after which to flush the log file (alias LogFlushFreq). Specifies how often data is written to the log file. Set the value to *n* so that data is written to the log file every *n* lines. For example, set the value to 1 to write every line to the log file. Set the value to 0 (default value) to allow the operating system to determine when to write data to the log file.

Number of Restarts (alias NumRestart). Specifies the number of times that a multithreaded server component can be restarted if it exited with errors in less than the time set for Minimum Up Time. This parameter works with Auto Restart to determine whether multithreaded server components will be restarted. This parameter also works with the Minimum Up Time parameter to determine the number of restart attempts in a time interval allowed for a component (NumRestart multiplied by MinUpTime). If a component instance cannot be restarted after this time interval, then no new restarts are attempted. (In this situation, the component instance will not be running.) The default value for this parameter is 10.

Number of Retries (alias NumRetries). Specifies the number of retries for recovery. This parameter works with the Retry Interval and Retry Up Time parameters to reconnect multithreaded server components to the database if database connectivity has been lost.

Number of Sessions per SISNAPI Connection (alias SessPerSisnConn). Specifies how many sessions can be multiplexed (shared) through each SISNAPI connection, which helps to reduce the number of open network connections. SISNAPI connections are those between the Siebel Application Interface and the Application Object Manager. If Number of Sessions per SISNAPI Connection is -1, then all of the sessions are created through only one SISNAPI connection. The default value for this parameter is 20. However, while 20 is a good value to use for user sessions, it does not apply to incoming HTTP requests from other systems, for example, EAI HTTP Adapter access.

OM - Data Source (alias DataSource). Specifies the Application Object Manager data source.

OM - Named Data Source Name (alias NamedDataSource). Lists the named subsystems that the Application Object Manager preloads when it initializes. That is, all of the data sources that the Application Object Manager might use are listed in the value.

OM - Model Cache Maximum (alias ModelCacheMax). Specifies the size of the cache for model objects (also known as cached sessions) in object manager-based server components, such as Workflow Process Manager. Each model in the cache creates two database connections for the life of the model. (One connection is for insert, update, and delete operations. The other connection is for read-only operations.) The model cache improves performance for the object manager-based server components, and it is generally recommended not to disable this parameter. The default value is 10. A value of 0 disables this parameter, and the maximum setting for this parameter is 100. For more information about setting this parameter, see *Siebel Performance Tuning Guide*.

OM - Preload SRF Data (alias PreloadSRF). Determines whether to preload all of the Siebel runtime repository information upon startup of an Application Object Manager server component. If the value is False (the default setting), then the Siebel runtime repository data is loaded only at first task or Siebel Web Client connection request, which can delay the startup page.

Note: Do not set OM - Preload SRF Data to True for single-threaded object manager components, which include EAI receivers such as MQSeries Server Receiver. If OM - Preload SRF Data is True, the Siebel Server will try to initialize the EAI receiver twice, causing it to fail.

OM - Resource Language Code (alias ResourceLanguage). Specifies the language code used for Application Object Manager resources. Each language has its own three-letter code identifier. For example, ENU identifies U.S. English. For more information, see *Siebel Global Deployment Guide*.

OM - Save Preferences (alias SavePreferences). Set the value for this parameter to False to prevent the Application Object Manager from creating or reading user preference files (file extension is .spf). When True (the default value), the Application Object Manager creates a user preference file when a user logs in, if one does not already exist.

OM - Timed Statistics (alias TimedStats). Enables the use of the statistics in the Administration - Server Management screen, Statistics view. Statistics include Average Connect Time (seconds), Average Response Time (milliseconds), and Average Think Time (seconds). Restart the Siebel Server for this parameter to take effect. The statistics are refreshed on completion of each task, so a specific user session must log out for the statistics for that session to be reflected in the Statistics screen. This is an advanced parameter.

When a task for a component completes its operation, both generic and component-specific statistics roll up to the component level. Only generic statistics roll up to the Siebel Server level. The statistics data will be reset when the component is restarted.

Password (alias Password). Specifies the database user password. This parameter specifies the password for the account referenced by the User Name parameter. Both the user name and password are prompted for during the initial configuration of the Siebel Server. The User Name and Password parameters are used to connect to the

database for automatic startup of background mode components, for example. See also the description for the Auto Startup Mode parameter in "[Siebel Server Parameters](#)" on page A-16 and [Table A-3](#).

Process VM Usage Lower Limit (alias MemoryLimit). Sets the virtual memory usage threshold (in megabytes). A component process that reaches this threshold is recycled. The parameter to enable this feature is Memory Usage Based Multithread Shell Recycling. Use this parameter to remedy your application only if excessive memory usage created by memory leaks seems to be occurring.

Process VM Usage Upper Limit (alias MemoryLimitPercent). Specifies the percentage above the value of Process VM Usage Lower Limit at which a fast shutdown is triggered.

Retry Interval (alias RetryInterval). Defines the time interval before a series of retries are made for recovery. This parameter works with the Number of Retries and Retry Up Time parameters to reconnect multithreaded server components to the database if database connectivity has been lost.

Retry Up Time (alias RetryUpTime). Specifies the minimum up-time for a new set of retries for recovery. This parameter works with the Number of Retries and Retry Interval parameters to reconnect multithreaded server components to the database if database connectivity has been lost.

Session Keepalive Timeout (alias SessKeepAlive). Specifies the time that a task waits for a message from the client before timing out. When the time-out interval passes, the task ends the client session. The default value is 7200 seconds (two hours). This is a hidden parameter.

SISNAPI Connection Maximum Idle Time (alias ConnIdleTime). Configures the connection timeout between the Siebel Application Interface and the Siebel Server. Valid values are numeric, specifying the period of idle time (in seconds) after which the connection is disconnected by the component. See the following table for parameter setting descriptions. It is recommended that you set this parameter to a value slightly below the firewall connection timeout value. The default value is -1.

Table A-4 Values for ConnIdleTime Parameter

Parameter Value	Description
Less than 0	Disables this feature.
Any value between 0 and 30	Configures the minimum value for this parameter, 30 seconds.
Greater than 30	Configures that value in seconds.

Note: There is no direct relationship between this parameter and the session timeout setting for the Siebel Application Interface. The SISNAPI Connection Maximum Idle Time parameter controls the connection behavior while the session timeout setting controls the user session behavior. For more information, see the *Siebel Installation Guide* for the operating system you are using.

SISNAPI - Log Traffic (alias LogTraffic). Specifies whether the Application Object Manager records a log of all of the Siebel Internet Session API (application programming interface) messages. SISNAPI is a session-based remote procedure call (RPC) designed to support high responsiveness between the Siebel Server and client applications.

Sleep Time (alias SleepTime). Specifies the time to sleep between iterations (in seconds). This parameter is used for the sleep time of component processes running in background mode when the Siebel Server is idle.

SQL Trace Flags (alias SQLFlags). The flags for tracing of SQL statements. If this parameter is set to 1, then every SQL statement issued by the component tasks is logged to the information log file for each task. If this parameter is set to 2, then each SQL statement is logged in addition to information about the number of parse, execute, and fetch calls, and timing information about each type of call.

Static Port Number (alias PortNumber). Specifies the network port number on which a component listens for client requests. If no value is specified, then a unique port number is generated dynamically for each component, starting at port number 49150 and higher, depending on the number of components configured and the occupied ports above this number.

The Siebel Connection Broker component (alias SCBroker), which provides intraserver load balancing, listens on the port specified by this parameter. For more information, see "[About Siebel Connection Broker \(SCBroker\)](#)" on page 8-3.

This parameter applies to interactive, batch, and background mode components, with the exception of all of the Application Object Manager components. The port number, whether static or dynamic, is hidden from the end user and is provided primarily so that administrators can fix the port numbers used by a component, for firewall configuration. If you are configuring this parameter, then select a port number either below 49150 or high enough to make sure that there are no conflicts with dynamically generated port numbers.

Trace Flags (alias TraceFlags). Specifies the flags for component-specific tracing information. This parameter is used to turn on various types of component-specific tracing. See the documentation for individual Siebel Server components for a description of how to set this parameter for each component.

Use IP Address (alias UseIPAddress). Specifies whether to construct the SISNAPI connection strings using the IP address instead of the hostname. The default value is True. Changing the value to False affects performance because the hostname must be looked up each time it connects.

Use Shared Log File (alias LogUseSharedFile). Specifies whether all of the tasks within a component process log to a shared file. When set to False, one log file for each task is generated.

User Name (alias Username). Specifies the database user name. This parameter specifies the user name of the database account that is used by the Siebel Server or Siebel Server components that are not started interactively or in batch mode by the Siebel Server Manager. The password for this database account must be specified by the Password parameter. Both the user name and password are prompted for during the initial configuration of the Siebel Server. The User Name and Password parameters are used to connect to the database for automatic startup of background mode components and for other purposes. See also the description for the Auto Startup Mode parameter in "[Siebel Server Parameters](#)" on page A-16 and [Table A-3](#).

When you run component tasks from the Server Manager GUI, the value for the User Name parameter is used because the tasks are submitted as component jobs and started using the Server Request Broker server component, which uses the User Name parameter value. When you run component tasks from the Server Manager command-line interface, in the case of manually started batch or background mode components, the User Name parameter is that of the user who starts tasks on these components.

Parameters in Siebel Application Configuration Files

This appendix includes information about some of the parameters in Siebel application configuration files. It includes the following topics:

- [Overview of Parameters in Siebel Application Configuration Files](#)
- [About Siebel Application Configuration Files](#)
- [Editing Siebel Application Configuration Files](#)
- [Configuration Parameters Index](#)
- [Description of Siebel Application Parameters](#)
- [Data Source Parameters](#)

Overview of Parameters in Siebel Application Configuration Files

This appendix includes information about the Siebel application configuration files and some of the parameters that these files might contain. Most of the parameters that are documented here are used by Siebel Business Applications in a Siebel Mobile Web Client or a Siebel Web Client deployment.

Note: Not all of the parameters used by Siebel Business Applications are described in this book. Many parameters are primarily described elsewhere on *Siebel Bookshelf*, while some parameters are not documented on *Siebel Bookshelf*.

Where you configure parameters for Siebel Business Applications depends on your type of client deployment:

- For a Siebel Mobile Web Client deployment, you configure parameters in a configuration file (.cfg). Examples of configuration files include `siebel.cfg`, used by Siebel Sales, and `uagent.cfg`, used by Siebel Call Center. For more information, see ["About Siebel Application Configuration Files"](#) on page B-2 and ["Editing Siebel Application Configuration Files"](#) on page B-3.
- For a Siebel Web Client deployment, you primarily configure parameters as component parameters for the Application Object Manager component or as named subsystem parameters. In either case, you use the Siebel Server Manager to configure the parameter. For more information, see ["About Application Object Manager Parameters"](#) on page 9-3.

Note: Application Object Manager components might also use some parameters in configuration files located on the Siebel Server.

The remaining topics in this appendix include the following:

- ["About Siebel Application Configuration Files"](#) on page B-2 lists some configuration files and their associated Siebel Business Applications.
- ["Editing Siebel Application Configuration Files"](#) on page B-3 describes how you can edit a Siebel application configuration file.
- ["Configuration Parameters Index"](#) on page B-4 provides a partial list of configuration parameters and provides references to where they are documented in more detail.

In many cases, when you set the equivalent parameter for an Application Object Manager component, for Siebel Web Clients, the alias of the parameter that appears in the Siebel Server Manager GUI is prefixed by CFG. The full parameter name also appears in the GUI.

For example, for Siebel Mobile Web Clients, you set the parameter ApplicationSplashText in the configuration file to determine the text that appears on a splash screen when a user starts a Siebel application. For a Siebel Web Clients, you set the parameter Application Splashtext (alias CFGApplicationSplashText) on the relevant Application Object Manager component.

- ["Description of Siebel Application Parameters"](#) on page B-9 describes some of the parameters that are listed in ["Configuration Parameters Index"](#) on page B-4.
- ["Data Source Parameters"](#) on page B-11 describes some of the data source parameters that are listed in ["Configuration Parameters Index"](#) on page B-4.

Note: For Siebel Web Clients, many of these parameters can be set as named subsystem parameters for the relevant data source. In many cases, the parameter alias that appears in the Siebel Server Manager GUI is prefixed by DS. For example, the ConnectString parameter that you set in the [ServerDataSrc] section of an application configuration file appears as Data source Connect String (alias DSConnectString) for the Server Datasource named subsystem in the Siebel Server Manager GUI.

About Siebel Application Configuration Files

[Table B-1](#) lists several configuration files and their associated Siebel Business Applications. Your installation might contain additional configuration files besides those listed.

The configuration files are located in the `SIEBEL_CLIENT_ROOT\bin\LANGUAGE` directory on the Siebel Mobile Web Client. The name of the configuration file varies, depending on the application that you are using. Separate configuration files are provided for each supported language.

Table B-1 *Some Siebel Business Applications and Associated Configuration Files*

Siebel Application	Configuration File
Siebel Call Center	uagent.cfg

Table B-1 (Cont.) Some Siebel Business Applications and Associated Configuration

Siebel Application	Configuration File
Siebel Marketing	market.cfg
Siebel Partner Manager	pmanager.cfg
Siebel Sales	siebel.cfg
Siebel Service	sfs.cfg

The initial values for the parameters in the configuration files are either predefined by Siebel Business Applications or defined using the values that you specify during the initial configuration or at other times.

Some parameter values might include the notation $\$(param_name)$. These parameter values are substituted automatically, for example, during a client installation or local database initialization. For example, the value of the ConnectString parameter for a data source that has not yet been configured appears as follows:

```
ConnectString = $(ConnectString)
```

This parameter value is updated when you initialize the local database for a Siebel Mobile Web Client. For more information about initializing the local database, see *Siebel Remote and Replication Manager Administration Guide*. See also the *Siebel Installation Guide* for the operating system you are using.

Editing Siebel Application Configuration Files

The Siebel application configuration files are plain-text files, and can be edited manually using a text editor. You can add parameters and their values or change values for existing parameters.

Caution: When you edit the configuration files, use a text editor that does not perform unwanted character substitutions or change the file's character encoding to formats other than UTF-8. For example, use Microsoft Notepad instead of Microsoft Word or WordPad.

There are many reasons why you might edit configuration files. For example, you might want to do so at some point after the installation and initial configuration in order to enable or disable certain functionality and features. As appropriate, you must make changes in all of the configuration files for the applications that you are using. For each new application that you create, you must copy and edit a configuration file to suit your needs.

Note: If a configuration parameter is not needed, then you can comment it out by inserting a semicolon at the start of the line.

To edit a Siebel application configuration file

1. Create a backup copy of the existing configuration file for which you want to edit parameter values, and save that file as a backup file.
2. Using any suitable text editor, such as Notepad, open the default version of the configuration file.

3. Edit parameter values, as necessary, to obtain the application behavior that you require.
4. Run a test using the configuration file that you edited.
5. If there is an error in your test, then correct the error and try again, or restore the configuration file from the backup file.
6. If no error occurs and the edit that you made has the result that you wanted, then use the modified configuration file.

Configuration Parameters Index

[Table B-2](#) contains an alphabetical listing of some of the configuration parameters from Siebel application configuration files such as `siebel.cfg` or `uagent.cfg`. This list shows the name of the section in which each parameter can be found and identifies where the parameter is documented (within [Table B-3](#) and [Table B-5](#)). This list is not comprehensive.

Table B-2 Index of Configuration Parameters

Configuration Parameter Name	Section Name	Where Documented and Description
AccessDir	[Siebel]	"AccessDir" on page B-9
AllowAnonUsers	[InfraUIFramework]	<i>Siebel Security Guide</i>
ApplicationName	[Siebel]	"ApplicationName" on page B-9
ApplicationPassword	Applicable security adapter sections, such as: [ADSIAdpt] [LDAPSecAdpt]	<i>Siebel Security Guide</i>
ApplicationSplashText	[Siebel]	"ApplicationSplashText" on page B-9
ApplicationTitle	[Siebel]	"ApplicationTitle" on page B-9
ApplicationUser	Applicable security adapter sections	<i>Siebel Security Guide</i>
BaseDN	Applicable security adapter sections	<i>Siebel Security Guide</i>
CancelQueryTimeOut	[InfraUIFramework]	<i>Siebel Applications Administration Guide</i>
CaptionPrefix	[Siebel]	"CaptionPrefix" on page B-9
CaseInsensitive	Applicable data source sections, including: [LOCAL_XE] [SAMPLE_XE] [ServerDataSrc] [GatewayDataSrc]	"CaseInsensitive" on page B-12
ClientRootDir	[Siebel]	"ClientRootDir" on page B-10
CommConfigCache	[Communication]	<i>Siebel CTI Administration Guide</i>
CommConfigManager	[Communication]	<i>Siebel CTI Administration Guide</i>
CommConfigManagerName	[Communication]	<i>Siebel CTI Administration Guide</i>
CommEnable	[Communication]	<i>Siebel CTI Administration Guide</i>
CommLocalDriver	[Communication]	<i>Siebel CTI Administration Guide</i>
CommLogDebug	[Communication]	<i>Siebel CTI Administration Guide</i>

Table B–2 (Cont.) Index of Configuration Parameters

Configuration Parameter Name	Section Name	Where Documented and Description
CommLogFile	[Communication]	<i>Siebel CTI Administration Guide</i>
CommMaxLogKB	[Communication]	<i>Siebel CTI Administration Guide</i>
CommMaxMsgQ	[Communication]	<i>Siebel CTI Administration Guide</i>
CommReleaseLogHandle	[Communication]	<i>Siebel CTI Administration Guide</i>
CommReqTimeout	[Communication]	<i>Siebel CTI Administration Guide</i>
ComponentName	[Siebel]	"ComponentName" on page B-10
ConnectString	Applicable data source sections, including: [LOCAL_XE] [SAMPLE_XE] [ServerDataSrc] [GatewayDataSrc]	"ConnectString" on page B-12 (data sources)
ContactLogin	Applicable data source sections	"ContactLogin" on page B-12
CredentialsAttributeType	Applicable security adapter sections	<i>Siebel Security Guide</i>
DataSource	[Siebel]	"DataSource" on page B-10
DebugLevel	[EMail]	<i>Siebel Email Administration Guide</i>
DefaultMailClient	[EMail]	<i>Siebel Email Administration Guide</i>
DisableExecuteRetry	[ServerDataSrc]	"DisableExecuteRetry" on page B-12
DisableReverseProxy	[InfraUIFramework]	<i>Siebel Security Guide</i>
DLL	Applicable data source sections, including: [LOCAL_XE] [SAMPLE_XE] [ServerDataSrc] [GatewayDataSrc]	"DLL" on page B-12
Docked	Applicable data source sections, including: [LOCAL_XE] [SAMPLE_XE] [ServerDataSrc]	"Docked" on page B-12
DockConnString	Applicable data source sections, including: [LOCAL_XE]	"DockConnString" on page B-12
DockRecvTxnsPerCommit	Applicable data source sections	"DockRecvTxnsPerCommit" on page B-13
DockRepositoryName	[Siebel]	"DockRepositoryName" on page B-10
DockTxnsPerCommit	Applicable data source sections, including: [LOCAL_XE]	"DockTxnsPerCommit" on page B-13
EditFieldCaption	[InfraUIFramework]	<i>Configuring Siebel Business Applications</i>
EditFieldType	[InfraUIFramework]	<i>Configuring Siebel Business Applications</i>

Table B-2 (Cont.) Index of Configuration Parameters

Configuration Parameter Name	Section Name	Where Documented and Description
Enable	[DataCleansing] [DeDuplication]	<i>Siebel Data Quality Administration Guide</i>
EnableFQDN	[Siebel]	<i>Siebel Installation Guide</i> for the operating system you are using
EnableInlineForList	[InfraUIFramework]	If the applet mode property is set to Edit List, then the functions Edit, New, and Query work in-line, that is, in the list applet, when EnableInlineForList is set to True. The default value is True. Set to False to turn off this behavior.
EnablePersonalization	[Siebel]	" EnablePersonalization " on page B-10
EnableScripting	[Siebel]	" EnableScripting " on page B-10
EnterpriseServer	Applicable data source sections, including: [LOCAL_XE] [ServerDataSrc]	" EnterpriseServer " on page B-13
eProdCfgNumOfCachedCatalogs	[InfraObjMgr]	<i>Siebel Performance Tuning Guide</i>
eProdCfgNumOfCachedObjects	[InfraObjMgr]	<i>Siebel Performance Tuning Guide</i>
eProdCfgNumofCachedWorkers	[InfraObjMgr]	<i>Siebel Performance Tuning Guide</i>
eProdCfgSnapshotFlg	[InfraObjMgr]	<i>Siebel Performance Tuning Guide</i>
FileSystem	Applicable data source sections, including: [SAMPLE_XE] [ServerDataSrc]	" FileSystem " on page B-13
FQDN	[Siebel]	<i>Siebel Installation Guide</i> for the operating system you are using
GatewayAddress	Applicable data source sections, including: [ServerDataSrc]	" GatewayAddress " on page B-13
GatewayDataSrc	[DataSources]	" GatewayDataSrc " on page B-11
Hidden	Applicable data source sections, including: [GatewayDataSrc]	" Hidden " on page B-13
InsensitivityFactor	Applicable data source sections, including: [LOCAL_XE] [SAMPLE_XE] [ServerDataSrc] [GatewayDataSrc]	" InsensitivityFactor " on page B-14
InsUpdAllCols	Applicable data source sections	" InsUpdAllCols " on page B-14
IntegratedSecurity	Applicable data source sections	" IntegratedSecurity " on page B-14
Local	[DataSources]	" Local " on page B-11
LocalDbODBCDataSource	[Siebel]	" LocalDbODBCDataSource " on page B-10

Table B–2 (Cont.) Index of Configuration Parameters

Configuration Parameter Name	Section Name	Where Documented and Description
LoginView	[InfraUIFramework]	<i>Siebel Security Guide</i>
MaxCachedCursors	Applicable data source sections, including: [LOCAL_XE] [SAMPLE_XE] [ServerDataSrc]	"MaxCachedCursors" on page B-14
MaxCachedDataSets	Applicable data source sections, including: [LOCAL_XE] [SAMPLE_XE] [ServerDataSrc]	"MaxCachedDataSets" on page B-14
MaxConnections	Applicable data source sections	"MaxConnections" on page B-14
MaxCursorSize	Applicable data source sections, including: [ServerDataSrc]	"MaxCursorSize" on page B-15
MaxDepthOfTheQuery	[InfraObjMgr]	"MaxDepthOfTheQuery" on page B-10
MessageBarUpdateInterval	[Siebel]	<i>Siebel Applications Administration Guide</i>
MultiCurrency	[Siebel]	"MultiCurrency" on page B-10
NonSQL	Applicable data source sections	"NonSQL" on page B-15
NumberOfListRows	[InfraUIFramework]	<i>Siebel Object Types Reference</i>
PasswordAttributeType	Applicable security adapter sections	<i>Siebel Security Guide</i>
PersonalizationLog	[Siebel]	"PersonalizationLog" on page B-10
Port	Applicable security adapter sections	<i>Siebel Security Guide</i>
PrefetchSize	Applicable data source sections, including: [ServerDataSrc]	"PrefetchSize" on page B-15
PrimaryEnterprise	Applicable data source sections, including: [GatewayDataSrc]	"PrimaryEnterprise" on page B-15
RemoteSearchServer	[Siebel]	"RemoteSearchServer" on page B-10
RemoteSearchServerPath	[Siebel]	"RemoteSearchServerPath" on page B-10
ReportDataDir	[XMLPReports]	<i>Siebel Reports Guide</i>
ReportsDir	[Siebel]	"ReportsDir" on page B-10
ReportOutputDir	[XMLPReports]	<i>Siebel Reports Guide</i>
ReportsODBCDataSource	[Siebel]	"ReportsODBCDataSource" on page B-11
RepositoryFile	[Siebel]	"RepositoryFile" on page B-11
RequestServerName	[InfraObjMgr]	This parameter is the name of the Siebel Server that services requests from the Siebel client.
RequiredIndicator	[InfraUIFramework]	<i>Siebel Developer's Reference</i>

Table B–2 (Cont.) Index of Configuration Parameters

Configuration Parameter Name	Section Name	Where Documented and Description
ReverseFillThreshold	Applicable data source sections, including: [LOCAL_XE] [SAMPLE_XE] [ServerDataSrc]	"ReverseFillThreshold" on page B-15
RolesAttributeType	Applicable security adapter sections	<i>Siebel Security Guide</i>
Sample	[DataSources]	"Sample" on page B-11
ScriptingDLL	[Siebel]	"ScriptingDLL" on page B-11
SearchDefName	[Siebel]	"SearchDefName" on page B-11
SearchEngine	[Siebel]	"SearchEngine" on page B-11
SearchInstallDir	[Siebel]	"SearchInstallDir" on page B-11
SecAdptDllName	Applicable security adapter sections	<i>Siebel Security Guide</i>
SecAdptMode	[InfraSecMgr]	<i>Siebel Security Guide</i>
SecAdptName	[InfraSecMgr]	<i>Siebel Security Guide</i>
ServerDataSrc	[DataSources]	"ServerDataSrc" on page B-11
ServerName	Applicable security adapter sections	<i>Siebel Security Guide</i>
SharedCredentialsDN	Applicable security adapter sections	<i>Siebel Security Guide</i>
SharedModeUsersDir	[Siebel]	"SharedModeUsersDir" on page B-11
ShowMessageBar	[Siebel]	<i>Siebel Applications Administration Guide</i>
ShowWriteRecord	[InfraUIFramework]	<i>Siebel Partner Relationship Management Administration Guide</i>
SiebelExtMailClientAttDir	[EMail]	<i>Siebel Email Administration Guide</i>
SiebelUsernameAttributeType	Applicable security adapter sections	<i>Siebel Security Guide</i>
SingleSignOn	Applicable security adapter sections	<i>Siebel Security Guide</i>
SqlStyle	Applicable data source sections, including: [LOCAL_XE] [SAMPLE_XE] [ServerDataSrc]	"SqlStyle" on page B-15
SslDatabase	Applicable security adapter sections	<i>Siebel Security Guide</i>
SystemSWFName	[InfraUIFramework]	<i>Configuring Siebel Business Applications</i>
SystemSWSName	[InfraUIFramework]	<i>Configuring Siebel Business Applications</i>
TableOwner	Applicable data source sections, including: [LOCAL_XE] [SAMPLE_XE] [ServerDataSrc]	"TableOwner" on page B-16
TempDir	[Siebel]	"TempDir" on page B-11

Table B–2 (Cont.) Index of Configuration Parameters

Configuration Parameter Name	Section Name	Where Documented and Description
TreeNodeX (several parameters that are similarly named, for example, TreeNodeCollapseCaption)	[InfraUIFramework]	<i>Configuring Siebel Business Applications</i>
TrustToken	Applicable security adapter sections	<i>Siebel Security Guide</i>
Type	[DataCleansing] [DeDuplication]	<i>Siebel Data Quality Administration Guide</i>
UpperCaseLogin	Applicable data source sections	" UpperCaseLogin " on page B-16
UseDictionaryinTransactionLogging	Applicable data source sections	" UseDictionaryinTransactionLogging " on page B-16
UseAdapterUsername	Applicable security adapter sections	<i>Siebel Security Guide</i>
UseRemoteConfig	Applicable security adapter sections	<i>Siebel Security Guide</i>
UsernameAttributeType	Applicable security adapter sections	<i>Siebel Security Guide</i>
UserSWFName	[InfraUIFramework]	<i>Configuring Siebel Business Applications</i>
UserSWSName	[InfraUIFramework]	<i>Configuring Siebel Business Applications</i>
Version	[Siebel]	" Version " on page B-11
WebTemplatesVersion	[InfraUIFramework]	<i>Siebel Performance Tuning Guide</i>
XdoDir	[XMLPReports]	<i>Siebel Reports Guide</i>

Description of Siebel Application Parameters

[Table B–3](#) describes several Siebel application parameters. These parameters appear in the [Siebel] section of the configuration file and apply to Siebel Mobile Web Client or Siebel Developer Web Client.

For the Siebel Web Client, the parameters are defined as server parameters on the Application Object Manager, rather than defined in a configuration file. Some parameters might also apply to Siebel Tools and are defined in the tools.cfg file.

Table B–3 Siebel Application Parameters

Name	Description
AccessDir	Specifies the directory where Microsoft Access is installed.
ApplicationName	Name of the application object in the repository to use, such as Siebel Sales or Siebel Service. ApplicationName determines which splash screen appears and which set of menus is enabled.
ApplicationSplashText	Text that appears on a splash screen when starting up a Siebel application. The default varies by the application. If you are starting Siebel Sales, for example, then ApplicationSplashText is set to Siebel Sales by default.
ApplicationTitle	Changing the text in the ApplicationTitle parameter in the configuration file changes the Application Title value in the multi-value group applets and the Title that appears on the left side of the application title bar. As necessary, make this change in the appropriate configuration file for the intended application. For example, for Siebel Call Center, this parameter is set, in the file uagent.cfg, to <i>Siebel Call Center</i> .
CaptionPrefix	Allows customizing of the title in the upper-left corner of the Siebel client application. Reads Siebel by default.

Table B-3 (Cont.) Siebel Application Parameters

Name	Description
ClientRootDir	Specifies the directory where the Siebel client software is installed.
ComponentName	<p>Specifies the Siebel Anywhere configuration that is used during version check. Navigate to the Administration - Siebel Anywhere screen, then the Configurations view, to see the configurations.</p> <p>Change the setting for this parameter if you want this configuration file to be version-checked by a specific Siebel Anywhere configuration.</p> <p>For example, if you want to check the version of Siebel Business Applications used at one facility with the version used at another facility, then create two Siebel Anywhere configurations appropriately named. Then, in the configuration file for each set of users, enter a different value for the ComponentName parameter.</p> <p>It is recommended that you use only alphanumeric characters plus dashes and normal parentheses for the ComponentName parameter. If you want to use the Priority upgrade feature, then the maximum character length for the Upgrade Component name is 40.</p>
DataSource	Name of the default data source that appears in the Connect to drop-down list in the Siebel login screen. Must correspond to an existing data source defined in the configuration file. By default, this parameter is set to Local.
DockRepositoryName	Allows the application to read repository information straight from the database, rather than from the Siebel runtime repository. The value matches the repository used for generating the Siebel runtime repository.
EnablePersonalization	<p>Must be set to True to activate the personalization (content targeting) functionality. Siebel workflow processes will not execute properly until personalization events are reloaded.</p>
EnableScripting	<p>True or False. Enables use of Siebel Visual Basic or Siebel eScript.</p> <p>Setting this parameter to False also disables browser scripts in addition to server scripts.</p>
LocalDbODBCDataSource	Name of the ODBC data source that is set up to access the local database. It is used by a variety of features in the Siebel Business Applications and in Siebel Tools. Do not modify it, because it is already correctly configured for the Siebel client or Siebel Tools.
MaxDepthOfTheQuery	<p>Allows you to increase the maximum parse depth of a query with a large search specification, including, for example, a large number of OR or AND clauses.</p> <p>You can set this parameter in the application configuration file for the Siebel Mobile Web Client or Developer Web Client, or set it in the tools.cfg file for Siebel Tools. Set it in the [InfraObjMgr] section.</p> <p>Alternatively, you can set this parameter for the Siebel Enterprise. The full name of the server parameter is Maximum depth of the query. For more information about this parameter, see "Siebel Enterprise, Server, and Component Parameters" on page A-11 (see "Generic Parameters" on page A-18).</p>
MultiCurrency	True or False. Enables multicurrency support.
PersonalizationLog	<p>Add the following to the configuration file to view a log of all personalization activity:</p> <pre>PersonalizationLog = "C:\personalization.txt"</pre> <p>where C: is the drive where you want to store the log. The log can help you debug your rules, events, and actions.</p>
RemoteSearchServer	True or False. True indicates that searches are performed on a remote computer. False indicates that searches are performed on a local computer.
RemoteSearchServerPath	Indicates the name of the remote computer that performs searches.
ReportsDir	Directory where reports are installed. It is typically left blank.

Table B–3 (Cont.) Siebel Application Parameters

Name	Description
ReportsODBCDataSource	Name of ODBC data source used to connect to external modules.
RepositoryFile	Name of the Siebel runtime repository to use.
ScriptingDLL	Name of the shared library that implements Siebel Visual Basic or Siebel eScript. If the Siebel Server runs on a UNIX server computer, and you plan to use Siebel eScript, then set the value of ScriptingDLL to sscfjs.so.
SearchDefName	Search definition from Siebel Tools to be used for searching. For more information about search, see <i>Siebel Search Administration Guide</i> .
SearchEngine	Defines the search engine to use for search. You set this parameter to the value that identifies the search engine. If your search engine is Oracle Secure Enterprise Search, then you set it to SES. For more information about search engine administration, see <i>Siebel Search Administration Guide</i> .
SearchInstallDir	Set this parameter to the directory where your search engine is installed. For more information about search engine administration, see <i>Siebel Search Administration Guide</i> .
SharedModeUsersDir	Directory where user preference files are stored. It is typically left blank. Otherwise, it must be set to a directory under a network shared drive, but it cannot be set to the shared drive itself. For example, if \\yourserver\common is the network shared drive, then you cannot set SharedModeUsersDir to \\yourserver\common. Instead, set SharedModeUsersDir to a directory under \common.
TempDir	Directory where temporary files are created.
Version	Represents the version of a file. This parameter is for internal use only and is automatically maintained by Siebel Anywhere. When you create an upgrade kit for the configuration file, Siebel Anywhere increments this version string appropriately, based on the version information from the Upgrade Components view. Note: When you perform a Siebel Anywhere upgrade, you must manually upgrade files from the upgraded Siebel client directory to the Siebel Server directory.

Data Source Parameters

This section describes parameters that pertain to the [DataSources] section of the configuration file and to the individual data source sections that follow.

These parameters apply only to Siebel Mobile Web Client. For the Siebel Web Client. The parameters are defined as server parameters on the Application Object Manager.

Parameters for DataSources Section

Table B–4 lists data sources in the Siebel configuration file, which appear in the [DataSources] section. Each data source also has its own section specifying parameters that apply to this data source.

Table B–4 Data Sources

Name	Function
Local	Defines parameters for connecting to the local database.
Sample	Defines parameters for connecting to the sample database.
ServerDataSrc	Defines parameters for connecting to the Siebel database.
GatewayDataSrc	Defines Siebel Gateway parameters.

Note: If you want to prevent a data source from being displayed as a choice in the Connect To: portion of the Siebel login screen, then add two slash characters (//) in front of the data source in the [DataSources] section of the configuration file. For example: //Sample = Sample.

Parameters for Individual Data Source Sections

Table B-5 lists parameters that specify properties associated with the different data sources listed under [DataSources]. Each data source section defines the properties of the particular data source.

Table B-5 Data Source Parameters

Name	Comment
CaseInsensitive	<p>True or False. If it is True, then the client is notified to work with the database in case-insensitive mode.</p> <p>See also the description of the InsensitivityFactor parameter for data sources.</p> <p>Note: Queries against fields of type DTYPE_ID are always case-sensitive, even if the CaseInsensitive parameter is set to True. For more information, see <i>Siebel Applications Administration Guide</i>.</p>
ConnectionString	<p>Database-dependent string that defines how to connect to the database (also referred to as the <i>connection string</i>).</p> <p>The ConnectionString parameter is also used to specify the Siebel Gateway computer in the GatewayDataSrc section. In the Siebel Mobile Web Client's configuration file, you must specify the Siebel Gateway's hostname, preferably in a fully qualified form like <i>node.domain.xxx</i>. Failure to specify this parameter correctly results in the server administration screens being inaccessible.</p> <p>For more information about using connection strings for different server databases, see the <i>Siebel Installation Guide for the operating system you are using</i>.</p>
ContactLogin	<p>True or False. If it is True, then it indicates that the corresponding data source uses contact login, rather than employee login. Because a contact user is generally not associated one-to-one with a database account, you must use a security adapter to support contact users.</p> <p>If it is False, then the data source is using employee login, rather than contact login.</p>
DisableExecuteRetry	<p>True or False. When set to True, this parameter prevents the client from resending a query to the database layer if an error occurs such as a network error or session kill.</p>
DLL	<p>Name of the DLL file to use for the database connector code. The names differ depending upon whether you are using Oracle Database, Microsoft SQL Server, IBM DB2, and so on.</p>
Docked	<p>Determines which database connection the application login screen for a Mobile Web Client defaults to. For example, if Docked is True in the [ServerDataSrc] section of the configuration file and Docked is False in the [LOCAL_XE] section of the configuration file, then the application login screen defaults to the server database rather than the local database. The values used in this example are the default values.</p>
DockConnString	<p>Name of the docking server (Siebel Remote Server). It is the computer name of the Siebel Server against which the Mobile Web Client synchronizes.</p>

Table B–5 (Cont.) Data Source Parameters

Name	Comment
DockRecvTxnsPerCommit	<p>Number of transactions received by the Mobile Web Client before a commit is issued to the database. The default value for this parameter is 10. Change the setting to:</p> <ul style="list-style-type: none"> ■ A higher value if you have a fast network connection, such as a LAN. Increasing the value can provide better performance when synchronizing the Mobile Web Client with the server. ■ A lower value if you have a lower-bandwidth network connection, such as a modem.
DockTxnsPerCommit	Number of transactions processed before a commit is issued to the database.
EnterpriseServer	Name of the Siebel Enterprise Server.
FileSystem	<p>Specifies how the Mobile or Siebel Developer Web Client (for administrative purposes) accesses the Siebel File System. The value of this parameter cannot exceed 2048 characters. Generally, FileSystem and other parameters identified in this table are set during the Siebel client installation.</p> <p>Mobile Web Client. The following scenario for setting the FileSystem parameter applies to the Siebel Mobile Web Client. Install the Siebel File System locally on a Mobile Web Client, so that it is accessible when the client is not connected to the network and can be synchronized using Siebel Remote:</p> <p>Set the following parameter, where <i>FS_location</i> is a UNC location or a drive-letter path to the location on the client computer where the local Siebel File System was installed:</p> <pre>FileSystem = FS_location</pre> <p>Developer Web Client. The following scenarios for setting the FileSystem parameter apply to the Siebel Developer Web Client when used for administrative purposes. Make sure that users on the Siebel Developer Web Client have physical access privileges for the Siebel File System directories:</p> <ul style="list-style-type: none"> ■ If the Developer Web Client installation uses File System Manager (alias FSMSrvr), then set the following parameters: <pre>FileSystem = *FSM* GatewayAddress = Siebel_Gateway_hostname EnterpriseServer = Siebel_Enterprise_Server_name</pre> ■ If the Developer Web Client installation does <i>not</i> use FSMSrvr, then set the following parameter, where <i>FS_location</i> is a UNC location or a drive-letter path to the location on a network computer where the Siebel File System was installed: <pre>FileSystem = FS_location</pre> <p>If your networked Siebel File System resides on a UNIX server, then you require a cross-platform NFS file system mounting tool to connect from Siebel Developer Web Clients running on Windows computers.</p>
GatewayAddress	Host name or IP address of the Siebel Gateway.
Hidden	True or False. Determines if the data source shows up in the login screen's picklist of data sources.

Table B-5 (Cont.) Data Source Parameters

Name	Comment
InsensitivityFactor	<p>Set to a positive integer value (default is 2). Applies only when the CaseInsensitive parameter is True for the data source. The value controls the number of characters in each string that are treated as case-insensitive in a query. Not all database vendors support case-insensitivity efficiently, so this feature provides an approximate solution.</p> <p>See also the description of the CaseInsensitive parameter for data sources.</p> <p>The following is an example SQL WHERE clause generated when searching for an opportunity named New, when InsensitivityFactor is set to 2.</p> <pre>WHERE ((S_OPTY.NAME LIKE 'ne%' OR S_OPTY.NAME LIKE 'Ne%' OR S_OPTY.NAME LIKE 'nE%' OR S_OPTY.NAME LIKE 'NE%')) AND UPPER(S_OPTY.NAME)=UPPER('New')</pre> <p>This example shows that all of the permutations of the first two letters of the string <i>New</i> are checked. With a higher factor, the number of permutations grows exponentially, and performance suffers.</p> <p>Note: Do not set this parameter to a value higher than 13.</p>
InsUpdAllCols	<p>True or False. Ordinarily, when the Siebel application generates INSERT or UPDATE statements to send to the database, the actual statement contains only the columns where data is present or has changed. When there are situations where you generate many statements on a particular table, the differences in the values being updated might prevent you from using an array interface supported by the DBMS.</p> <p>When this feature is set to True, all of the columns are present in all INSERT and UPDATE statements. Where two statements are issued against the same table in the same business component as part of a batch operation, this setting automatically enables the statements to use any existing array feature of the DBMS.</p>
IntegratedSecurity	<p>True or False. When True, the Siebel client is prevented from prompting the user for a user name and password when the user logs in. Facilities provided in your existing data server infrastructure determine whether the user is allowed to log into the database.</p> <p>This parameter is set for your server data source. However, it is supported for Oracle Database and Microsoft SQL Server databases only. The default value is False.</p> <p>For additional information, refer to your third-party documentation. For Oracle Database, refer to the OPSS and REMOTE_OS_AUTHENT features. For Microsoft SQL Server, refer to Integrated Security.</p>
MaxCachedCursors	<p>Specifies the maximum number of SQL cursors that can be cached in memory for a database connection. The default is 16.</p> <p>Caching SQL cursors can improve response time and CPU usage because an SQL cursor does not have to be prepared each time it is executed. If memory usage is not a concern, then you might consider increasing the value of this parameter.</p>
MaxCachedDataSets	<p>Specifies the maximum number of data sets that can be cached in memory for a database connection. The default is 16.</p> <p>A data set is the set of records that has been retrieved by the execution of a business component. Data-set caching applies only to those business components for which the Cache Data property has been set in Oracle's Siebel Tools.</p> <p>Caching data sets for frequently visited business components can improve response time and CPU usage. If memory usage is not a concern, then you might consider increasing the value of this parameter.</p>
MaxConnections	<p>Number of connections that can be made to the data source database server.</p>

Table B-5 (Cont.) Data Source Parameters

Name	Comment
MaxCursorSize	Sets the total number of rows that can be returned in a result set. MaxCursorSize is intended for use <i>only</i> with IBM DB2 for OS/390 and z/OS, and must be set as described in <i>Implementing Siebel Business Applications on DB2 for z/OS</i> . If you are using another database, then do not set this parameter to any value other than the default value (-1), or database behavior is adversely affected. MaxCursorSize and PrefetchSize are used together, and they must be set to the same value. See also the description for the PrefetchSize parameter.
NonSQL	True or False. Setting that indicates that the data source does not use an SQL DBMS to retrieve its data. Use this parameter only in conjunction with a specialized business component that your company builds internally. Never use this parameter arbitrarily.
PrefetchSize	Sets the number of rows that the Siebel application reads initially as part of a query execution. PrefetchSize is intended for use <i>only</i> with IBM DB2 for OS/390 and z/OS, and must be set as described in <i>Implementing Siebel Business Applications on DB2 for z/OS</i> . If you are using another database, then do not set this parameter to any value other than the default value (-1), or database behavior is adversely affected. MaxCursorSize and PrefetchSize are used together, and they must be set to the same value. See also the description for the MaxCursorSize parameter.
PrimaryEnterprise	The name of the Enterprise Server that you want to administer from the client computer. Set this parameter to view or change information in the server administration views.
ReverseFillThreshold	When the current query contains many rows, it might be very inefficient for the user to click End try to display and read them all sequentially. For this reason, the customer might configure a threshold value to invert the current sort, re-execute the query, and fill the data buffers from the end. These internal operations are hidden from the user.
SqlStyle	Indicates what kind of SQL to send to the database that you are using. When generating SQL to send to a DBMS, the application constructs the SQL statement to suit the particular DBMS. The value of this parameter is automatically set by the Siebel client installer or by initial server configuration, according to database information that you specified. The local database or Sample Database, based on Oracle Database XE, uses OracleCBO (the same as Oracle Database Enterprise). IBM DB2 and Microsoft SQL Server use the style applicable to the particular DBMS.

Table B-5 (Cont.) Data Source Parameters

Name	Comment
TableOwner	In a database, tables are identified by both their owner and their name. When queries that reference tables are issued, the table owner must be included in those references (for example, SIEBEL.S_EVT_ACT, where SIEBEL is the table owner). Siebel Server infrastructure and system management components, such as SRBroker and SRProc, read the value of this parameter. For Application Object Manager server components, you specify the table owner by setting a value for the Datasource Table Owner (alias DSTableOwner) named subsystem parameter.
UpperCaseLogin	The default is False. If it is set to True, then the user ID, when a user logs in, is converted to uppercase before it is sent to the database for authentication. This value is applicable only if the database is used for authentication. The value of the parameter is ignored when SecurityAdapter is set to a nonempty value. Use this parameter if you want to enforce a policy of having all of the database accounts in uppercase on a case-sensitive database, but you do not want users to worry about case when they type in their user names. Note: The value of UpperCaseLogin does not affect the password.
UseDictionaryInTransactionLogging	To avoid the diccache.dat creation while using the Developer Web Client connected to the database server, add this parameter to the [ServerDataSrc] section in the configuration file. <code>UseDictionaryInTransactionLogging = False</code> Note: This parameter is not supported if you plan to use Siebel Remote and synchronize between client and server. If you plan to perform only testing and administration tasks connected against the database server, then you will not be affected. For Siebel Remote testing, use the Siebel Web Client and the Siebel Mobile Web Client.

A

Active defined components state, described, 4-23
administrative memory, about, 9-2
Alert Level parameter, described, A-18
alias
 command, creating alias for a, 7-24
 command, deleting alias for a, 7-24
application environment, diagram, 2-2
Auto Restart parameter, described, A-18
Auto Startup Mode parameter, described, A-16

B

background mode components, described, 2-6
batch mode components, described, 2-6
business service, starting repeating component, 6-8

C

commands
 alias, creating for, 7-24
 alias, deleting for, 7-24
Communication Transport parameter,
 described, A-16
component definition parameter, changing
 (Parameter Management command), 7-20
component groups
 about and using, 2-7
 creating (Server Manager command), 7-13
 current component group status, listing (List
 command), 7-9
 deleting (Server Manager command), 7-15
 enterprise, disabling (Server Manager
 command), 7-14
 enterprise, enabling for (Server Manager
 command), 7-14
 listing component groups (List command), 7-9
 predefined Siebel Server components (table), A-4
 run state, changing to Offline mode (Server
 Manager command), 7-14
 run state, changing to Online mode (Server
 Manager command), 7-14
 server, assigning to (Server Manager
 command), 7-14
 server, disabling (Server Manager

 command), 7-15
 server, enabling on a (Server Manager
 command), 7-14
 server, removing (Server Manager
 command), 7-15
component groups, configuring
 component group, creating, 4-24
 defined components, defined states, 4-22
 synchronizing server components, 4-17
component jobs, changing the component, 4-17
Component Priority Level Timeout parameter,
 described, A-16
component recycling, 4-30
component requests, administration
 component request, deleting during its
 creation, 6-9
 repeated component requests, about running, 6-8
component type parameter, changing (Parameter
 Management command), 7-20
components
 component definition parameter, deleting
 (Parameter Management command), 7-21
 component definition, copying (Component
 Definition command), 7-16
 component definition, deleting (Component
 Definition command), 7-16
 component definition, disabling (Component
 Definition command), 7-16
 component definition, enabling (Component
 Definition command), 7-16
 component parameter, deleting (Parameter
 Management command), 7-21
 current component status, listing (List
 command), 7-9
 defined, 2-6
 definition commands (Server Manager
 command), 7-15
 event log level for a component on a Siebel Server
 (Event Logging command), 7-23
 new component, creating (Component Definition
 command), 7-15
 new component, creating (Server Manager
 command), 7-15
 parameter, changing (Parameter Management
 command), 7-20
 task, listing values for (Server Manager

- command), 7-9
- types, described, 2-7
- Compression Type parameter, described, A-16
- configuration
 - Mobile Web Client, B-2
- configuration file
 - editing, B-1, B-4
 - Siebel Application Object Manager, used to modify parameters, 9-3
- configuration parameters
 - [DataSources] section of CFG file, B-11, B-12
 - [Siebel] section of CFG file, B-9
 - alphabetical index, B-4
 - Siebel applications, B-9
- copying component definition (Component Definition command), 7-16
- Creating defined components state, described, 4-23

D

- data sources parameters, B-11, B-12
- DB Multiplex - Min Number of Dedicated DB Connections parameter, described, A-19
- DB Multiplex - Min Number of Shared DB Connections parameter, described, A-19
- Default Tasks parameter, described, A-19
- defined components
 - about, 2-7
 - defined states, 4-22
- Delete After field, setting to delete component requests, 6-9
- Delete Units field, setting to delete component requests, 6-9
- deleting
 - alias for a command, 7-24
 - component definition (Component Definition command), 7-16
 - component definition parameter (Parameter Management command), 7-21
 - component groups (Server Manager command), 7-15
 - component parameter (Parameter Management command), 7-21
 - enterprise parameters (Parameter Management command), 7-20
 - named subsystem (Named Subsystem Management command), 7-21
 - named subsystem parameter (Parameter Management command), 7-21
 - Siebel Server parameter (Parameter Management command), 7-20
- Disabled assigned component state, described, 4-10, 4-21

E

- editing configuration files, B-1
- Enabled assigned component state, described, 4-10, 4-21
- EnabledTC parameter, described, A-19

- Encryption Type parameter, described, A-16
- enterprise parameters
 - administering, 7-20
 - changing (Parameter Management command), 7-20
 - changing (Server Manager command), 7-20
 - deleting (Parameter Management command), 7-20
 - list of, A-15
- Error Flags parameter, described, A-19
- events
 - event log level for a component, changing (Event Logging command), 7-23
 - event types, listing (Event Logging command), 7-23
 - log level for a component, changing on a Siebel Server (Event Logging command), 7-23
 - log level for Siebel Server, changing (Event Logging command), 7-23
- exiting srvmngr program, 7-8
- Export Status Size parameter, described, A-19

F

- File System Manager (FSM), B-13
- File System Manager, about and the Siebel File System, 2-10
- files
 - commands, reading from file, 7-7
 - output, starting or stopping spooling to, 7-7

G

- Gateway
 - See Siebel Gateway

H

- help, on Server Manager commands, 7-7
- Host Name parameter, described, A-17

I

- Inactive defined components state, described, 4-23
- Indexspace Name parameter, described, A-15
- interactive mode components, described, 2-6

L

- Language Code parameter, described, A-20
- list command
 - available columns for a list, listing, 7-12
 - listing the columns returned, 7-24
 - modifying the output of an individual command, 7-12
 - output of the list command, configuring, 7-12
 - show specific columns, configuring list command to, 7-24
 - state values, listing current, 7-11
- list definitions for component, parameters, state values, and statistics, 7-22

loading preferences, 7-25
Log Archive Keep parameter, described, A-17
Log Maximum Segments parameter, described, A-17
Log Print Timestamp parameter, described, A-20
Log Segment Size parameter, described, A-17

M

market.cfg file, B-3
Maximum depth of the query parameter, described, A-20
Maximum MT Servers parameter, described, A-21
Maximum Processes parameter, described, A-21
Maximum Tasks parameter, described, A-21
memory allocation, three areas of allocation described, 9-2
Memory Usage Based Multithread Shell Recycling parameter, described, A-21
Microsoft Access and AccessDir parameter, B-9
Minimum MT Servers parameter, described, A-21
Minimum Up Time parameter, described, A-22
multiple defined components, about, 2-7

N

named subsystems
 creating (Named Subsystem Management command), 7-21
 deleting (Named Subsystem Management command), 7-21
 modifying (Named Subsystem Management command), 7-21
 new named subsystem, creating (Named Subsystem Management command), 7-21
 parameter, deleting (Parameter Management command), 7-21
Number of lines after which to flush the log file parameter, described, A-22
Number of Restarts parameter, described, A-22
Number of Retries parameter, described, A-22

O

ODBC Data Source parameter, described, A-15
OM - Save Preferences, description, A-23
OM - Timed Statistics, description, A-23

P

parameters
 component definition parameter, changing (Parameter Management command), 7-20
 component parameter, changing (Parameter Management command), 7-20
 component type parameter, changing (Parameter Management command), 7-20
 current parameter values, listing (List command), 7-10
 enterprise parameter, changing (Parameter Management command), 7-20

 enterprise parameter, changing (Server Manager command), 7-20
 enterprise parameters, deleting (Parameter Management command), 7-20
 generic parameters, list of, A-18
 server parameter, changing (Parameter Management command), 7-20
 Siebel Server parameters, administering, 4-5
 task parameter, changing (Parameter Management command), 7-20
Password parameter, described, A-23
pmanager.cfg file, B-3
port access, verifying, 3-6
predefined components, about, 2-7
preferences
 loading, 7-25
 saving, 7-24
Process Failure Diagnostics view, 4-2
Process VM Usage Lower Limit parameter, described, A-24
Process VM Usage Upper Limit parameter, described, A-24

R

Retry Interval parameter, described, A-24
Retry Up Time parameter, described, A-24
run task command, about and example, 7-18

S

server components, System Management server group, 8-1
Server Description parameter, described, A-17
server group
 assigning a Siebel Server to, 7-12
 connecting to a server group, 7-12
 unassigning a Siebel Server from a server group, 7-12
Server Manager. *See* Siebel Server Manager
Server Request Broker
 administering, about, 8-1
Server Request Processor
 about and components, 8-2
Server Shutdown Wait Time parameter, described, A-17
servers, starting server component (Server Manager command), 7-17
session mode components, listing tasks for (List command), 7-10
sfs.cfg file, B-3
sfscleanup. *See* Siebel File System cleanup utility
shared memory, about, 9-2
shutting down
 Siebel deployment, 5-2
 Siebel Server (Siebel Server Management command), 7-13
 Siebel Server auxiliary system components (Component Management command), 7-18
 Siebel Server component (Component

- Management command), 7-17
- Siebel Server nonsystem components (Component Management command), 7-18
- Siebel Server system components (Component Management command), 7-18
- svrvmgr program, 7-8
- Siebel Application Interface, B-3
- Siebel Application Object Manager
 - about, 9-1
 - environment, configuring, 9-2
 - memory allocation, three areas of allocation, 9-2
 - monitoring, about monitors levels, 9-6
 - parameters, configuration files (table of), 9-3
- Siebel applications, parameters in CFG file, B-9
- Siebel Call Center, configuration file for, B-2
- Siebel clients, about entities, 2-1
- Siebel database, about entities, 2-1
- Siebel deployment
 - shutting down, 5-2
 - starting up, 5-1
- Siebel Enterprise Server
 - about and setting parameters, 2-3
 - connections, refreshing (Environment command), 7-8
 - entities, about, 2-1
 - environment diagram, 2-2
- Siebel environment, table of entities, 2-1
- Siebel File System, 8-5
 - about, 8-5
 - about and the File System Manager, 2-10
 - entities, about, 2-1
 - file attachment directory, cleaning up using sfsccleanup, 8-11
 - file types processed, table of, 8-14
 - operation performed during processing (table), 8-14
 - parameter, described, A-15
- Siebel File System cleanup utility
 - about, 8-5
 - file attachment directory, cleaning up using, 8-11
 - file types processes, table of, 8-14
 - operation performed during processing (table), 8-14
- Siebel Gateway
 - about, 2-2
 - failure impact, about, 2-3
 - reinstalling (procedure), 3-8
 - reinstalling, cases for, 3-8
 - UNIX, checking status of Siebel Gateway system service, 5-7
 - UNIX, starting Siebel Gateway system service, 5-5
 - UNIX, stopping Siebel Gateway system service, 5-6
 - Windows, checking status of Siebel Gateway system service, 5-5
 - Windows, starting Siebel Gateway system service, 5-4
 - Windows, stopping Siebel Gateway system service, 5-4
- Siebel Management Pack, about, 2-10
- Siebel Marketing, configuration file for, B-3
- Siebel Partner Manager, configuration file for, B-3
- Siebel Repository parameter, described, A-15
- Siebel Root Directory parameter, described, A-17
- Siebel Sales, configuration file for, B-3
- Siebel Server
 - about and supported functions, list of, 2-3
 - auxiliary system components, shutting down (Component Management command), 7-18
 - auxiliary system components, starting (Component Management command), 7-18
 - component groups, about and using, 2-7
 - component modes, described, 2-6
 - component types, about, 2-7
 - component, auto start (Component Management command), 7-17
 - component, disabling (Component Management command), 7-18
 - component, enabling (Component Management command), 7-18
 - component, manual start (Component Management command), 7-17
 - component, shutting down (Component Management command), 7-17
 - component, starting (Component Management command), 7-17
 - current working server, setting (Environment command), 7-7
 - current working server, unsetting (Environment command), 7-7
 - event log level for a component, changing (Event Logging command), 7-23
 - event log level, changing (Event Logging command), 7-23
 - nonsystem components, shutting down (Component Management command), 7-18
 - nonsystem components, starting (Component Management command), 7-18
 - note, about reducing load on, 4-10
 - parameter, changing (Parameter Management command), 7-20
 - parameter, deleting (Parameter Management command), 7-20
 - reinstalling (procedure), 3-8
 - reinstalling, cases for, 3-8
 - shutting down (Siebel Server Management command), 7-13
 - starting (Siebel Server Management command), 7-13
 - system components, shutting down (Component Management command), 7-18
 - system components, starting (Component Management command), 7-18
 - system server, described for Windows and UNIX, 2-4
 - system service, what happens at startup (list of actions), 5-7
 - UNIX, starting Siebel Server system service, 5-9
 - UNIX, stopping Siebel Server system

- service, 5-10
- Windows, checking status of Siebel Server system service, 5-8
- Windows, starting Siebel Server system service, 5-8
- Windows, stopping Siebel Server system service, 5-8
- Siebel Server components
 - predefined Siebel Server components (table), A-4
 - synchronizing, when to synchronize, 4-17
- Siebel Server Manager, command-line interface
 - See also* Siebel Server
 - about using and using the interface, 2-5
 - command syntax, 7-6
 - commands, about, 7-5
 - component definition commands, list of, 7-15
 - component group definition commands, 7-13
 - component management commands, list of, 7-17
 - connections to other servers, about, 2-5
 - environment variables, list of commands, 7-7
 - event logging commands, list of, 7-23
 - help, getting, 7-7
 - List commands, list of, 7-8, 7-10
 - list definition commands, list of, 7-22
 - Named Subsystem Management commands, list of, 7-21
 - parameter manager commands, list of, 7-20
 - preferences file, creating aliases and configuring commands, 7-24
 - Siebel Server management commands, list of, 7-13
 - svrvmgr command-line output, adding header and footer information, 7-8
 - svrvmgr command-line output, removing header and footer information, 7-8
 - svrvmgr program, command-line flags (table of), 7-2
 - svrvmgr program, example parameters (table), 7-2
 - svrvmgr program, exiting, 7-8
 - svrvmgr program, starting, 7-1, 7-13
 - task management commands, list of, 7-18
- Siebel Server Manager, GUI
 - about, 4-1
 - about using and using the interface, 2-5
 - connections to other servers, about, 2-5
 - Siebel administrator responsibility, about granting, 4-2
- Siebel Server Name parameter, described, A-17
- Siebel Server parameters, list of, A-16
- Siebel Servers, listing available servers (List command), 7-8
- Siebel Servers, listing processes (List command), 7-10
- Siebel Service, configuration file for, B-3
- siebel.cfg file, B-3
- SISNAPI Connection Maximum Idle Time parameter, described, A-24
- Size of Error Buffer parameter, described, A-17
- Sleep Time parameter, described, A-25
- SQL tracing, SQL Trace Flags parameter, described, A-25
- SRProc. *See* Server Request Processor
- svrvmgr program
 - See* Siebel Server Manager, command-line interface
- start task command, about, 7-18
- starting
 - new task in background mode (Task Management command), 7-19
 - new task, stating in task mode (Task Management command), 7-19
 - server component (Server Manager command), 7-17
 - Siebel Gateway system service on UNIX, 5-5
 - Siebel Gateway system service on Windows, 5-4
 - Siebel Server (Siebel Server Management command), 7-13
 - Siebel Server auxiliary system components (Component Management command), 7-18
 - Siebel Server component (Component Management command), 7-17
 - Siebel Server nonsystem components (Component Management command), 7-18
 - Siebel Server system components (Component Management command), 7-18
 - svrvmgr program, 7-1, 7-13
- state values
 - current, listing (List command), 7-11
 - listing current (Server Manager command), 7-11
 - tasks, listing values for (Server Manager command), 7-11
- Static Port Number parameter, described, A-25
- statistics
 - current statistic values, listing (List command), 7-11
 - task, listing values for (Server Manager command), 7-12
- stopping
 - running task (Task Management command), 7-19
 - Siebel Gateway system service on UNIX, 5-6
 - Siebel Gateway system service on Windows, 5-4
- subsystems
 - listing (List command), 7-9
 - named subsystems, listing (List command), 7-9
- Synchronization Port parameter, described, A-17
- synchronizing Siebel Server components, when to synchronize, 4-17
- System Management server group
 - See* Server Request Broker

T

- Table Owner parameter, described, A-15
- Table Owner Password parameter, described, A-15
- Tablespace Name parameter, described, A-15
- tasks
 - background mode, starting new task in (Task Management command), 7-19
 - batch mode, running task in (Task Management command), 7-19

- paused tasks, resuming (Task Management command), 7-19
- running task, killing (Task Management command), 7-19
- running task, pausing (Task Management command), 7-19
- running task, stopping (Task Management command), 7-19
- session mode components, listing tasks for (List command), 7-10
- status of current tasks, listing (List command), 7-10
- task mode, starting new task in (Task Management command), 7-19

Trace Flags parameter, described, A-25

troubleshooting load balancing

- port access, verifying, 3-6

U

uagent.cfg file, B-2

UNIX

- Siebel Gateway system service, checking
 - status, 5-7
- Siebel Gateway system service, starting, 5-5
- Siebel Gateway system service, stopping, 5-6
- Siebel Server system service, starting, 5-9
- Siebel Server system service, stopping, 5-10
- Siebel Server, support of eScript, not VB, 9-2

Upgrade Component parameter, described, A-16

user memory, about, 9-2

User Name parameter, described, A-25

V

Visual Basic, Siebel Server support of, 9-2

W

Windows

- Siebel Gateway system service, checking
 - status, 5-5
- Siebel Gateway system service, starting, 5-4
- Siebel Gateway system service, stopping, 5-4
- Siebel Server system service, checking status, 5-8
- Siebel Server system service, starting, 5-8
- Siebel Server system service, stopping, 5-8