

Leasing User Guide
Oracle FLEXCUBE Universal Banking
Release 14.0.0.0.0

Part No. E88855-01

December 2017

Leasing User Guide
Oracle Financial Services Software Limited

Oracle Park

Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:

Phone: +91 22 6718 3000

Fax: +91 22 6718 3001

<https://www.oracle.com/industries/financial-services/index.html>

Copyright © 2007, 2017, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are “commercial computer software” pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

4.1.10	<i>Maintaining Branch /Currency Restriction</i>	4-44
4.1.11	<i>Restricting Customer Category</i>	4-47
4.1.12	<i>Defining Product Fields</i>	4-48
4.1.13	<i>Associating an MIS Group with the Product</i>	4-50
4.1.14	<i>Defining User Defined Fields</i>	4-51
4.2	Viewing Product Summary Details	4-51
4.3	Processing EMI on Lease	4-52
5.	Account Creation	5-1
5.1	Lease Account Details	5-1
5.1.1	<i>Maintaining Lease Account Details</i>	5-2
5.1.2	<i>Main Tab</i>	5-4
5.1.3	<i>Account Details Tab</i>	5-12
5.1.4	<i>Default Tab</i>	5-15
5.1.5	<i>Checklist Tab</i>	5-17
5.1.6	<i>Fields Tab</i>	5-19
5.1.7	<i>Components Tab</i>	5-20
5.1.8	<i>Charges Tab</i>	5-27
5.1.9	<i>Linkages Tab</i>	5-30
5.1.10	<i>Advices Tab</i>	5-31
5.1.11	<i>Credit Score Tab</i>	5-32
5.1.12	<i>Capturing Additional Details for Leasing</i>	5-33
5.2	Saving and Authorising Mortgage/Commitment Account	5-33
5.3	Multilevel Authorization of a Contract	5-33
5.4	Viewing Lease Account Summary Details	5-34
5.5	Maintaining Events Dairy	5-35
5.5.1	<i>Processed Events</i>	5-36
5.5.2	<i>Unprocessed Events</i>	5-37
6.	Capturing Additional Details for a Lease	6-1
6.1	Additional Details	6-1
6.1.1	<i>Viewing MIS Details of the lease</i>	6-2
6.1.2	<i>Viewing Account GL Balance</i>	6-4
6.1.3	<i>Viewing Internal Rate of Return (IRR) Details</i>	6-5
6.1.4	<i>Capturing Swift Message Details</i>	6-6
6.1.5	<i>Viewing Installment Details</i>	6-6
6.1.6	<i>Viewing Events Diary Details</i>	6-8
6.1.7	<i>Viewing Asset Values</i>	6-9
7.	Making Manual Disbursements	7-1
7.1	Lease Disbursement through 'Manual' Mode	7-1
7.1.1	<i>Disbursing a Lease through the 'Manual' Mode</i>	7-1
7.1.2	<i>Verifying the Check List Items</i>	7-5
7.1.3	<i>Capturing Values for the Event Level UDFs</i>	7-6
7.1.4	<i>Viewing the Default Details</i>	7-6
7.1.5	<i>Viewing the Charge Details Associated with the Event</i>	7-7
7.1.6	<i>Capturing the Advice Related Details</i>	7-7
7.1.7	<i>Viewing the Swift Message Details</i>	7-9
7.2	Authorizing a Manual Disbursement	7-9
7.3	Disbursing a Lease through 'Auto' Mode	7-10
7.3.1	<i>Processing for Down Payment</i>	7-10
8.	Operations	8-1

8.1	Leasing Payments Details	8-1
8.1.1	<i>Maintaining Leasing Payments</i>	8-1
8.1.2	<i>Partial Payment</i>	8-7
8.1.3	<i>Payments Simulation</i>	8-8
8.2	Saving and Authorising Leasing Payments	8-9
8.3	Viewing Leasing Payments	8-10
8.4	Leasing Amendments Details	8-11
8.4.1	<i>Leasing Amendments</i>	8-11
8.4.2	<i>Amendments Tab</i>	8-12
8.4.3	<i>Account Details Tab</i>	8-12
8.4.4	<i>Default Tab</i>	8-14
8.4.5	<i>Components Tab</i>	8-15
8.4.6	<i>Charges Tab</i>	8-16
8.4.7	<i>Saving and Authorizing Leasing Amendments</i>	8-16
8.4.8	<i>VAMI Simulation</i>	8-17
8.5	Maintaining Manual Status Change.....	8-18
8.6	Viewing Manual Status Change	8-19
9.	Batch Processes	9-1
9.1	Batch Processes.....	9-1
9.1.1	<i>Configuring Batch Processes</i>	9-1
9.1.2	<i>Defining Batch Processes</i>	9-3
9.1.3	<i>Initiating the Batch Process</i>	9-4
9.1.4	<i>Multi-threading of Batch Processes</i>	9-5
9.1.5	<i>Excess Amount Allocation Batch</i>	9-5
9.1.6	<i>Interest Posting (INTP Event)</i>	9-6
9.1.7	<i>Processing the CL Batch</i>	9-7
9.1.8	<i>Processing Minimum Amount Due Batch</i>	9-7
9.1.9	<i>Processing the EMI Change Batch (EMIC)</i>	9-8
9.2	Triggering User Defined Events	9-9
9.2.1	<i>Viewing MIS Details</i>	9-11
9.2.2	<i>Viewing Rate Details</i>	9-13
9.2.3	<i>Viewing Charge Details</i>	9-17
9.2.4	<i>Viewing Event Details</i>	9-17
9.2.5	<i>Viewing Event Fields</i>	9-18
10.	Annexure A	10-1
10.1	Accounting Entries for Leasing.....	10-1
10.2	Events.....	10-1
10.3	Accounting Roles.....	10-2
10.4	Amount Tags	10-3
10.5	Event-wise Accounting Entries	10-3
10.5.1	<i>Financial Lease</i>	10-3
10.5.2	<i>Operational Lease</i>	10-6
10.6	Event-wise Advices	10-8
10.7	LE SDEs	10-10
11.	Function ID Glossary	11-1

1. Preface

1.1 Introduction

This manual is designed to acquaint you with the Leasing module of Oracle FLEXCUBE.

The manual provides an overview of the module and guides you through the various steps involved in providing leasing facility to the customers of your bank or leasing company. You can further obtain information about to a particular field by placing the cursor on the relevant field and striking the <F1> key on the keyboard.

1.2 Audience

This manual is intended for the following User/ User Roles:

Role	Function
Back office data entry clerk	Input functions for contracts
Back office managers/officers	Authorization functions
Product Managers	Product definition and authorization
End of Day operators	Processing during End of Day/ Beginning of Day
Financial Controller/Product Managers	Generation of reports

1.3 Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

1.4 Organization

This manual is organized into the following chapters.

Chapter	Description
Chapter 1	<i>About this Manual</i> gives information on the intended audience. It also lists the various chapters covered in this User Manual.
Chapter 2	<i>Leasing — An overview</i> is a snapshot of the features that the module provides.
Chapter 3	<i>Maintenances and Operations</i> talks about maintaining various parameters at bank and branch level.
Chapter 4	<i>Defining a Leasing Product</i> talks about defining the attributes specific to setting up a leasing product.

Chapter 5	<i>Account Creation</i> details the process of setting up and maintaining lease accounts.
Chapter 6	<i>Capturing Additional Details for a Lease</i> explains the various additional functions required to maintain and process a lease account.
Chapter 7	<i>Making Manual Disbursements</i> deals with the additional details and changes that you can effect on a lease.
Chapter 8	<i>Operations</i> deals with the maintenance of payments and amendments, funding, status change, simulation of payments, rollover and so on which are related to a lease account.
Chapter 9	<i>Batch Processes</i> explains the processes configuring a batch for auto processing.
Chapter 10	<i>Annexure A</i> lists the event-wise accounting entries required for leasing.
Chapter 11	<i>Function ID Glossary</i> has alphabetical listing of Function/Screen ID's used in the module with page references for quick navigation.





1.5 Related Documents

You may need to refer to any or all of the following User Manuals while working on the Leasing module:

- Finances
- Core Services
- Core Entities
- Deposits
- Procedures
- Settlements
- Profit
- Charges and Fees
- Tax
- User Defined Fields

1.6 Glossary of Icons

This User Manual may refer to all or some of the following icons:

Icons	Function
	Exit
	Add row
	Delete row
	Option List

2. Leasing - An Overview

The important features of the Leasing module of Oracle FLEXCUBE are discussed in depth in this chapter.

A Lease can be defined as a contract where a party being the owner (lessor) of an asset (leased asset) provides the asset for use by the lessee at a consideration (rental), either fixed or dependent on any variables, for a certain period (lease period), either fixed or flexible, with an understanding that at the end of such period, the asset, subject to the embedded options of the lease, will either be returned to the lessor or disposed off as per the lessor's instructions.

Leasing is nothing more than a method of paying for the use of an asset over a specified period of time. Though it seems very similar to the concept of renting, they are very different.

This chapter contains the following section:

- [Section 2.1, "Elements in a Lease Structure"](#)
- [Section 2.2, "Product Definition Facility"](#)
- [Section 2.3, "Methods of Interest Application"](#)
- [Section 2.4, "Methods of Interest Calculation and Payment"](#)
- [Section 2.5, "Flexible Repayment Schedule Set Up"](#)
- [Section 2.6, "Defining Grace Periods"](#)
- [Section 2.7, "Tracking the Status of a Lease"](#)
- [Section 2.8, "Supported Tax Types"](#)
- [Section 2.9, "Automatic Processing of Different 'Events'"](#)
- [Section 2.10, "Compensation on Pre-payment"](#)
- [Section 2.11, "Value Dated Amendments"](#)

2.1 Elements in a Lease Structure

This section contains the following topics:

- [Section 2.1.1, "Parties to a Lease"](#)
- [Section 2.1.2, "Leased Asset"](#)
- [Section 2.1.3, "Lease Period"](#)
- [Section 2.1.4, "Types of Lease"](#)
- [Section 2.1.5, "Lease Rental"](#)
- [Section 2.1.6, "Down Payment"](#)
- [Section 2.1.7, "Residual Amount"](#)

2.1.1 Parties to a Lease

There are two parties to a lease: the owner called the lessor and the user called the lessee. The lessor is the person who owns the asset and gives it on lease. The lessee takes the asset on lease and uses it for the period of the lease. *Ownership is no pre-condition for leasing.* Technically, in order to be a lessor, one does not have to own the asset; one has to have the right to use the asset. Thus, a lessee can be a lessor for a sub-lessee, unless the parent lessor has restricted the right to sub-lease.

2.1.2 Leased Asset

The subject of the lease is the asset, article or property to be leased. The asset may be anything – an automobile, land, factory, or consumer durable. Only tangible assets can be leased, you cannot lease intangible assets, since one of the prime elements of a lease is handing over possession, along with the right to use. Hence, intangible assets are assigned, whereas tangible assets may be leased.

The concept of leasing will have the following limitations:

- What cannot be owned cannot be leased. Thus human resources cannot be 'leased'.
- While lease of movable properties can be affected by mere delivery, immovable property is incapable of deliveries in the physical sense. Most countries have specific laws relating to transactions in immovable properties: if the law of the land requires a procedure for a lease of immovable or real estate, such procedure should be complied.
- A lease is structurally a rental for the lease period: with the understanding that the asset will be returned to the lesser after the period. Thus, the asset must be capable of re delivery. It must be durable (at least during the lease period), identifiable and severable. The existence of the leased asset is an essential element of a lease transaction – the asset must exist at the beginning of the lease and at the end on the lease term. Non-existence of the asset, for whatever reason, will be fatal to the lease.

2.1.3 Lease Period

The term of lease, or lease period, is the period for which the agreement of the lease shall be in operation. As an essential element in a lease is redelivery of the asset by the lessee at the end of the lease period, it is necessary to have a period of lease. During this certain period, the lessee may be given a right of cancellation, and beyond this period, the lessee may be given a right of renewal, but essentially, *a lease should not amount to a sale*, i.e. the asset should not be given permanently to the lessee.

2.1.4 Types of Lease

Leases can be broadly classified into two:

- Financial Lease
- Operational Lease

2.1.4.1 Financial Lease

In a Financial Lease, though the device used is leasing, the purpose and effect is virtually financing – leasing for the purpose of financing. However the generic differences between a lease and a lease mentioned earlier still remain. The lessor will provide the money needed by the lessee to buy an asset; in return the payments by the lessee will be in the form of lease rentals. The lease amount is the amount that has been financed. A Financial Lease is a 'lease look-alike'. This lease should be treated like a lease with the lease amount as the principal and a interest charged.

2.1.4.2 Operational Lease

It is a non-financial lease. Any other lease other than a financial lease is an operating lease. In a financial lease, the lessor does not operate the asset he leases; he merely finances it. The word 'operating lease' is not applied to indicate that the lessor 'operating' the asset, but only as a contra-distinction to Financial Leases. Therefore, any lease where the lessor takes a risk other than a plain financial risk is an operating lease. This lease should be treated like a lease with no principal and the entire lease amount as a special interest that is paid in installments.

2.1.5 Lease Rental

The lease rental represents the consideration for the lease transaction. This is the amount that the lessee pays the lessor.

If it is a Financial Lease Transaction, the rentals will simply be the recovery of the lessor's principal, and a certain rate of return on outstanding principal, i.e. the rentals can be seen as bundled principal repayment and interest.

If it is an Operating Lease Transaction, the rental might include several elements depending upon the costs and risks borne by the lessor, such as:

- Interest on the lessor's investment
- If the lessor bears any repairs, insurance, maintenance or operation costs, the charges for such cost.
- Depreciation of the asset
- Servicing charges or packing charges for providing a package of the above service.

2.1.6 Down Payment

Down Payment is the upfront payment made by the lessee at the beginning of the lease. This is a surrogate for the margin or borrower contribution in case of lease transaction. In the case of financial lease, the down payment will be entirely towards the principal and in the case of operational lease; the entire payment will be an income.

2.1.7 Residual Amount

Simply put, 'Residual Value' means the value of the leased equipment at the end of the lease term. If the lease contains a buy out option to buy the asset at the residual amount at the end of the lease, this is the price at which the lessee can buy the asset from the lessor at the end of the lease.

It is common practice to have residual amount for Financial Leases, but it is also possible for Operational Leases to have residual amount.

2.2 Product Definition Facility

A Product is a specific service, or scheme, that you offer your customers. A Leasing product is a specific Leasing scheme that is offered to customers.

While setting up the module, the bank or the Leasing Company can define the various leasing schemes that it offers as products. For each product, it can also define 'attributes', or in other words, the terms and conditions. When a user at the bank or leasing company actually processes a lease, it can be associated with a product. The lease acquires the terms defined for the product that it involves. However, you can allow a user to change the inherited attributes of a lease, while processing, to suit a special customer.

2.2.1 Advantages of Defining a Product

When defining a scheme as a product, the bank can specify the following details:

- Tenor and interest preferences
- Type of interest that is applicable
- Minimum, maximum and standard rates applicable
- Compensation interest and grace days (for lease)

- Standards schedules applicable
- Ledgers to which the accounting entries should be posted (at different events such as booking, amendment, rollover, etc)

The product is defined only once. Therefore, you need not specify the basic details, every time a lease is entered into Oracle FLEXCUBE. This feature drastically reduces processing time, thus allowing a bank to focus on and take advantage of, the opportunities in the market.

2.3 Methods of Interest Application

In Oracle FLEXCUBE, it is possible to define multiple interest and charges. That is, you can specify the interest and charge that you would like to levy at the different events in the lifecycle of a lease.

Interest can be calculated based on a rate, or a flat amount. Interest rates may be:

- Fixed
- Floating – Periodic Rate revision is possible
- Special

You can define tier and slab structures to compute charges. You can also define a minimum and a maximum charge, as well as a compensation for defaulted schedules.

2.4 Methods of Interest Calculation and Payment

The default interest calculation basis is 30 (Euro)/ 360.

The repayment schedules for interest can be defined, for each transaction. Depending on the mode of payment, the interest will be liquidated either automatically or manually, according to the schedule defined.

Accrual of Interest

The frequency of interest accrual, whether daily, monthly, quarterly, half-yearly, or annual, can be specified for a product during set up. This specification will apply, to the accruable components of all leases involving the product.

The system accrues interest whenever you make a backdated rate change. An accrual, to the extent of a repayment, is automatically carried out at the time of repayment.

The module supports amendments and payments for previous accrual periods. Subsequent accruals will correct any adjustments that are to be made due to these actions.

The Lease module allows you to accrue interest at the product level. Rather than accrue interest for each lease involving a product, and then update the ledgers of the accrued interest individually, the bank can accrue interest for each contract involving the product, and pass a consolidated entry to the ledgers.

2.5 Flexible Repayment Schedule Set Up

Using the Lease module, you can define flexible schedules for the payment of principle, interest, commission and fees. Schedules for the payment of the various components can be defined individually, or otherwise. The schedules would be amortized based on reducing balances.

2.6 Defining Grace Periods

A bank using this module can define a grace period for the products it offers. This specification would apply to all contracts involving the product. A compensation profit will be applied in case of default in payment, on expiry of the grace period. Compensation will not be applied if the payment is made during the grace period. In case the payment is not made, the compensation will be calculated from the day the payment is outstanding.

2.7 Tracking the Status of a Lease

The Lease module of Oracle FLEXCUBE, allows you to define the various status, into which overdue lease should move. The module allows a bank to define:

- The number of overdue days from which a lease should be classified under a status
- Whether accruals should be stopped on reaching a status
- Whether accruals should be reversed for a status
- The asset account to which defaulted lease should be transferred (if they are to be reported separately)
- The notices to be generated for the benefit of the customer

Movement of a lease from one status to another can be either automatic, or manual. Lease, both regular and past due, can be *tracked*, automatically, across several user-defined status.

2.8 Supported Tax Types

Oracle FLEXCUBE supports the processing of a Withholding and an Expense type of tax.

Tax can be computed based on either the liquidation amount or the schedule amount. The bank can define tax rates as slabs or tiers and define a minimum and maximum tax amount that could apply. The bank could bear the tax (Expense) or charge the customer for it (withholding).

2.9 Automatic Processing of Different 'Events'

A lease contract goes through different stages in its lifecycle. These stages are referred to as events in Oracle FLEXCUBE. Events can be defined as Booking, Amendment, Liquidation, etc.

Once a lease contract is initiated, Oracle FLEXCUBE automatically processes all the events defined for it starting from initiation until liquidation. It processes the following automatically:

- Passes the appropriate accounting entries
- Generates the advices and messages specified for the event (including billing notices and delinquency notices to defaulters)
- Liquidates due schedules
- Accrues interest
- Applies compensation interest on default

In addition, you can automatically track overdue contracts and classify them into various statuses. For each status, you can specify preferences like whether accruals should be stopped, reversed, or, if the lease should be transferred to a different asset account.

2.10 Compensation on Pre-payment

You can levy compensation on premature payments. This compensation can be specified both in terms of a percentage and as a flat amount.

2.11 Value Dated Amendments

Amendments (changes to the Maturity Date, the Principal amount, the Interest Rate, Interest spreads, Residual Amount etc.) are possible on any lease contract, product, or group of contracts. These amendments can take effect as of back-value or future dates.

The zero-based interest accrual methodology ensures that interest accruals are recalculated and adjusted for back-valued amendments.

Subsidized residual amount can be changed during VAMI if subsidized residual amount is checked at the product level. Down payment of a lease can be changed during VAMI if there is an increase in amount financed.

3. Maintenances and Operations

Before you begin using the Leasing module, you must maintain the following information in the system:

Bank Parameters

These are parameters that you need to specify at the bank level. These will include the following:

- Interest calculation parameters
- Amount blocks on inactive accounts
- Splitting of accounting entries for the offset leg
- Site specific maintenances

Branch Parameters

These are parameters that you need to specify at the branch level. These will include the following:

- Branch Code
- Branch description
- Netting Parameters
- Process till Next working Day.
- Intraday job preferences
- Account Auto generation
- Account Mask
- User ref number generation
- Other Preferences

In addition, you also have to maintain the following:

Check Lists

For different events, you can maintain check lists. You can maintain the checklists based on the combination of event code and product code.

Written down Value (Current Asset value)

You can capture the written down value of an asset linked to a lease account. These will include the following:

- Account reference number
- Currency
- Written down date
- Written down value
- Remarks

Re-computation of insurance amount on changed/ new written down value will be processed during EOD for all accounts. Also, only the latest written down value can be amended

The above maintenances are discussed in the following sections in this chapter:

- [Section 3.1, "Maintaining Bank Parameters"](#)
- [Section 3.2, "Maintaining Branch Parameters"](#)
- [Section 3.3, "Maintaining Check Lists"](#)

- [Section 3.4, "Maintaining Written Down Value \(Current Asset Value\)"](#)
- [Section 3.5, "Viewing Written Down Value \(Current Asset Value\)"](#)

3.1 Maintaining Bank Parameters

You can maintain the bank parameters in the 'Lending – Bank Parameters' screen. You can invoke this screen by typing 'CLDBKPMPT' in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

Here you can capture the following details:

Bank Code

Specify the code that represents your bank

Include To date for Interest Calc

If you check this option, then accrual entries will be passed from the value date + 1 till the maturity date. However, if this box is not checked, then accrual entries will be passed from the value date till the maturity date - 1.

Amount Blocking for inactive account

Indicate whether an amount block needs to be imposed on an inactive account or not

Split Offset Leg

Check this box if you wish to have split accounting entries for the offset leg of a transaction. For example, if a certain transaction debits a particular GL and credits two different GLs (as

in off balance sheet entries), the system will pass two debit entries for the first GL to be in sync with the credit entries to the other GLs. If this option is not checked the accounting entries will be as under:

Dr/ Cr	Account	Amount
Dr	0000000 1	50
Cr	0000001 1	20
Cr	0000002 2	30

If this option is checked the accounting entries will be as under:

Dr/ Cr	Account	Amount
Dr	0000000 1	20
Cr	0000001 1	20
Dr	0000000 1	30
Cr	0000002 2	30

Achieve Processed Records from events diary

The parameter Reference Date, Frequency, Unit will be used to archive the processed records in Event Diary

The archival will be done in EOD by batch function. If this parameter is not set then no archive will be done.

Purge Inactive Loans

Specify the tenor in units of days, months and year, for which you want to keep the inactive loans for purging.

Cut off Transactions

Select the Cutoff GL from the option list. Transactions after 2:00 pm on a day will be considered on the next working day. The accounting entries for such transactions will be passed into the Cutoff GL and not the Settlement GL.

3.2 Maintaining Branch Parameters

You can maintain the branch parameters in the 'Leasing – Branch Parameters' screen. You can invoke this screen by typing 'LEDBRPMT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Branch parameters include the following:

Branch Code

You have to indicate the code of the branch for which the parameters have to be maintained. The codes of the various branches of your bank are available in the option list provided.

Branch Name

Based on the branch code selected, the branch name is defaulted here.

Process Till Next Working Day – 1

This specification will determine the day on which automatic events such as accrual, liquidation etc. falling due on a holiday, should be processed. If you select this option, events scheduled for a holiday will be processed on the last working day before the holiday.

Netting

GL Netting Accrual

Here, you need to indicate the netting preference for posting entries during accrual, liquidation and status change.

GL Netting Liquidation

If you opt to net, the system will post a single consolidated entry for a GL and Currency combination. If you do not select this option, entries are posted individually for each account.

GL Netting Status Change

Check this option to indicate that installment level status change should be done.

Netting of Notices across Accounts

The Netting of Notices across Accounts can be used to indicate that for or all accounts for which the payments falls due on a particular date, the requests for invoice generation should be consolidated.

Auto Allocate Part Payment

Check this option if you want to do a partial payment through auto allocation.

Settlement

The settlement accounts for processing lending transactions have to be specified here. You have to specify the Bridge GL/Account to be used for the settlement of the debit and credit legs of transactions that would be processed at your branch. You can select the accounts from the option lists provided for the same.

Account Auto Generated

You can select this option for automatic generation of account numbers. The system generates the account numbers automatically when you create customer accounts through the 'Account Details' screen. If this option is not checked, you have to capture the account number yourself.

Account Mask

Check this box to specify a format/mask for account numbers in order to maintain uniformity in the account numbers generated/captured across a branch. If you specify that account numbers should conform to a specific format, you have to specify the mask in the 'Account Mask' field.

User Ref no in Msgs

Check this box to indicate that the User Reference Number provided in the account screen has to be used in Tag 20 of MT103 and Tag 21 of MT202. If the box is unchecked, the loan account number will be used instead of the User Ref no.

Auto Gen User ref

Check this box to indicate that system should auto generate user ref no during account creation.

IRR Processing

Check this option to trigger the YACR (Yield Accrual) event for the branch batch.

Accrual Entries on Holidays

Check this option to determine whether the accrual entries due on the holidays should be passed as of the holiday itself or as on the working day before the holiday(s)/after the holiday(s) depending on the Process Till Next Working Day -1 option.

3.3 Maintaining Check Lists

You can maintain check list for different events using the 'Check List Maintenance' screen. The check lists that you maintain here will be validated during the execution of that event for a lease account.

You can invoke this screen by typing 'CLDCHKMT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows the 'Check List' application interface. At the top, there's a title bar 'Check List' and a toolbar with 'New' and 'Enter Query' buttons. Below the toolbar, there are several input fields: 'Module Code' (a dropdown menu), 'Product Description' (a text field), 'Product Code *' (a text field), and 'Event Code *' (a dropdown menu with 'Book' selected). Below these fields is a section titled 'Check List Detail' which contains a table with one row labeled 'Check List Item *'. The bottom of the window has a blue footer with labels: 'Input By Date Time', 'Authorized By Date Time', 'Modification Number', and checkboxes for 'Authorized' and 'Open'.

The following details have to be captured here:

Product Code

Specify the product code for which you need to maintain a check list. Alternatively, you can also select the product code from the adjoining option-list. All valid loans and leasing products that you have maintained in the system will be available for selection. You can also select the option 'All' select all the product codes.

Event Code

Select the event code for which check list items have to be maintained, from the drop down list.

Product Description

The product description is defaulted based on the product selected.

Check List Item

Specify the check list item name that you want to maintain for the selected event. The check list items that you maintain here will be validated by the system during that event, while processing the lease account.

3.4 Maintaining Written Down Value (Current Asset Value)

You can capture the written down value for an asset linked to a lease account using the 'Leasing Written Down Value' screen. To invoke this screen, click 'LEDWDVAL' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

The screenshot shows a software window titled "Leasing Written Down Value". At the top left of the window is a "New" button. Below this, there are five input fields: "Account *", "Currency", "Written Down Date *", "Written Down Amount", and "Remarks". At the bottom of the window, there is a "Fields" section with labels for "Maker", "Date Time:", "Mod No", "Record Status", "Checker", "Date Time:", and "Authorization". An "Exit" button is located in the bottom right corner of the window.

The following details need to be maintained here:

Account

Specify the account for which written down value needs to be captured. Alternatively, you can also select the account number from the adjoining option list. All active financial lease accounts will be available in the list of options.

Written Down Date

Specify the date from which the written down value should become effective. Alternatively, you can also select the date by clicking the adjoining calendar button.

Written down Value

Specify the value for the asset. The value has to be in the same currency as that of the lease account.

Currency

The currency of the lease account number is defaulted here.


Remarks

Here you can capture additional information, if any.

During insurance processing, system computes the insurance premium using the SDE 'WRITTEN_DOWN_VALUE'. The value for this SDE for a lease account is derived from the maintenance done in the 'Asset Details' screen. System picks up the value for the latest effective date and the insurance rate is applied on this value to arrive at insurance premium amount.

3.5 Viewing Written Down Value (Current Asset Value)

You can view the written down value for an asset linked to a lease account using the 'Leasing Written Down Value Summary' screen. You can invoke this screen by typing 'LESWDVAL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



You can query on records based on any or all of the following criteria:

- Authorization Status
- Record Status
- Account Reference Number
- Written Down Date

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Account Reference Number
- Written Down Date

4. Defining a Leasing Product

A product is a specific service that you offer your customers. For example, amongst other financial services, you may offer Financial Lease. Financial Lease can be of different types:

- Financial Lease provided for purchase of Agricultural Land
- Financial Lease provided for purchase of Non Agricultural Land

Financial Lease for purchase of Agricultural Land and Financial Lease provided for purchase of Non Agricultural Land are examples of specific services that you offer. All Financial Lease for purchase of Agricultural Land that you issue would involve the product, Financial Lease provided for purchase of Agricultural Land.

A product, helps classify the lease that you issue, according to broad groups (such as, for growing cash crops, non-cash crops etc.,) having some common features.

The other advantage of defining a product is that you can define certain general attributes for a product. These attributes will default to all contracts involving it.

In this chapter, we shall discuss the manner in which you can define attributes specific to a Leasing product.

You can create a leasing product in the 'Product' screen, invoked from the Application Browser. In this screen, you can enter basic information relating to a lease product such as the Product Code, the Description, etc.

This chapter contains the following sections:

- [Section 4.1, "Setting up Product"](#)
- [Section 4.2, "Viewing Product Summary Details"](#)
- [Section 4.3, "Processing EMI on Lease"](#)

4.1 Setting up Product

This section contains the following topics:

- [Section 4.1.1, "Setting up a Product Details"](#)
- [Section 4.1.2, "Defining Other Attributes of the Product"](#)
- [Section 4.1.3, "Specifying User Data Elements"](#)
- [Section 4.1.4, "Specifying Product Preferences"](#)
- [Section 4.1.5, "Specifying Components"](#)
- [Section 4.1.6, "Specifying Notices and Statements"](#)
- [Section 4.1.7, "Mapping Accounting Role to Product"](#)
- [Section 4.1.8, "Specifying Account Status"](#)
- [Section 4.1.9, "Specifying Events"](#)
- [Section 4.1.10, "Maintaining Branch /Currency Restriction"](#)
- [Section 4.1.11, "Restricting Customer Category"](#)
- [Section 4.1.12, "Defining Product Fields"](#)
- [Section 4.1.13, "Associating an MIS Group with the Product"](#)
- [Section 4.1.14, "Defining User Defined Fields"](#)

4.1.1 Setting up a Product Details

You can capture product details in the 'Product' screen. You can invoke the 'Product' screen by typing 'LEDPRMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Product Maintenance' window with a 'New' sub-window. The interface includes the following elements:

- Product Code***: A text input field with a red asterisk indicating it is required.
- Product Description**: A text input field.
- Slogan**: A text input field.
- Start Date**: A date input field.
- End Date**: A date input field.
- Remarks**: A text input field.
- Product Category**: A text input field.
- Product Type**: Radio buttons for 'Commitment' and 'Loan'.
- Leasing**: A text input field.
- Lease Type**: A dropdown menu currently showing 'Financial'.

At the bottom of the window, there is a navigation bar with the following links: User Data Elements | Preferences | Components | Role To Head | Account Status | Notices and Statements | Events | Credit Score | Minimum Amount Due Method | Branch and Currency Restriction | Customer Category Restriction | Product Fields | MIS | Fields. Below this, there are fields for Maker, Checker, Date Time, Mod No, Record Status, and Authorization Status, along with an Exit button.

In this screen, you can enter basic information about a product such as the Product Code, the Description, etc. Information related to specific attributes of a product such as end date, preferences, components, events etc. have to be defined in the respective sub-screens.

Product Code

Specify the unique identifier for the leasing product in Oracle FLEXCUBE.

Product Description

Enter a brief description to identify the product code.

Slogan

You can enter marketing punch line for any product you create. This slogan will be printed on all advices that are sent to the customers who avail of the product.

For example, if you set up a borrowing product called Money Multiplier, you could enter the slogan 'Watch your money grow with Money Multiplier.'

Product Category

The system displays the category of the product as 'Leasing'.

Start Date and End Date

A product can be defined to be active over a specific period. When you create a product, you can specify a 'Start Date' and 'End Date' for it. The product can only be used within the specified period (i.e. within the Start Date and End Date).

If you do not specify the Start Date, the branch date will be displayed as the Start Date.

If you do not specify an End Date for a product, it can be used for an indefinite period.

The start and end dates of a product come in handy when you are defining a product that you would like to offer over a specific period.

Remarks

When creating a product, you can enter information about the product intended for your bank's internal reference. This information will *not* be printed on any correspondence with the customer.

Leasing

Specify the following under leasing in the screen:

Lease Type

Select the type of lease from the adjoining drop-down list. This list displays the following values:

- Financial
- Operational

4.1.2 Defining Other Attributes of the Product

After specifying the basic details of a product, you can define finer attributes for the product in the appropriate buttons provided. Click on the button provided for this purpose. Each button is explained briefly in the table below:

Button	Description
User Data Elements	To define the UDEs and Components relating to the product
Preferences	To indicate your preferences specific to the product
Components	To specify the component details, schedule definition and formulae for the product
Notices and Statements	To specify details of notices and account statements to be issued to customers. These have to be generated for different events in the life cycle of a lease.
Role to Head	To specify accounting roles and account heads for the product. (The concept of accounting roles and heads is explained later)
Account Status	To indicate the status preferences for the product
Events	To specify events
Branch/Currency Rest	To define the branch and currency restrictions for the product
Customer Category Restriction	To Define the Customer Category Restrictions and Customer Access Restrictions for the Product

Fields	To associate User Define Fields(UDFs) i.e. Character Fields, Number Fields and Date Fields, with the product
MIS	To associate MIS details with a product.
Product Fields	To define additional fields that are available for use depending on the bank's requirement


Note

There are some fields in the product screens, to which input is mandatory. If you try to save a product without entering details in these fields, the product will not be saved.

When you save a product that you have created, your user ID will be displayed in the 'Input By' field and the date and time at which you saved the product in the 'Date/Time' field. The Status of the product will be updated as 'Unauthorized'. A product is available for use only after it has been authorized by another user.

4.1.3 Specifying User Data Elements

You can define the User Data Elements in the 'User Data Elements' screen. Invoke this screen by clicking 'User Data Elements' button. The following screen displays:



To define a User Data Element (UDE), you have to specify the following details in the screen:

User Data Elements ID

Data elements like the rate at which interest has to be applied, the tier structure based on which interest needs to be computed etc. are called **User Data Elements (UDEs)**. These are, in effect, elements for which you can capture the values. You have to specify a unique ID to identify the UDE in the system.

User Data Elements Description

You can also provide a brief description of the UDE being defined.

User Data Elements Type

UDE Type will describe the nature of the UDE. Select the type of UDE from the adjoining drop-down list. This list displays the following values:

- Amount
- Number
- Rate
- Rate Code

User Data Elements Currency

If the UDE type is 'Amount', you should specify the currency of the UDE. Specify a valid currency in which the UDE amount is counted. This adjoining option list displays all valid currencies maintained in the system. You can choose the appropriate one.

Minimum Value

Specify the floor limit for the UDE value. This means that the actual UDE value cannot be less than the rate specified here. Note that this amount has to be less than the maximum UDE value. The system will throw an error message if the minimum UDE value is greater than the maximum UDE value.

Maximum Value

Specify the ceiling limit for the UDE value. This means that the actual UDE value cannot be greater than the rate specified here. Note that this amount has to be greater than the minimum UDE value. The system will throw an error message if this value is less than the minimum UDE value.

4.1.4 Specifying Product Preferences

Preferences are the options that are available to you for defining the attributes of a lease product. These could be:

- The manner in which the system should handle schedules falling due on holidays
- The tenor details for the lease
- Whether receivables should be tracked for the lease etc.

The options you choose, ultimately, shape the product. These details are used for lease processing.

Click 'Preferences' button in the 'Product' screen to move to this section of the screen.

You should maintain the following preferences for the loan product:

4.1.4.1 Account Preferences tab

Rate

The exchange rate preferences include the following:

Rate

Indicate the exchange rate applicable for the product you are maintaining. The available options are:

- Mid Rate
- Buy/Sell Rate

By default, the Buy/Sell Rate is used.

Rate Type

Specify a valid type of the rate that should be used for the product. This adjoining option list displays all valid types of rate maintained in the system. You can choose the appropriate one.

The 'Rate' and 'Rate Type' are used in combination to determine the actual rate applicable for currency conversion.

The default value for Rate Type is 'STANDARD'. This means that, if you choose 'Mid Rate', the mid rate maintained for the STANDARD code is used for the loans created under the product.

Maximum Variance

Specify the maximum limit for rate variance. This is expressed in percentage. The variance between the exchange rate (specified for the product) and the rate captured for a loan (at the account level) should not be greater than the value specified here. If the exchange rate exceeds the maximum variance that you have defined for the product, the system will not allow you to save the loan. The transaction is rejected.

This value should be greater than the value for 'Normal Variance'.

Normal Variance

Specify the minimum/normal variance allowed for the rate. If the exchange rate variance between the exchange rate (specified for the product) and the rate captured for a loan exceeds the value specified here, the system will display an override message before proceeding to apply the exchange rate. The normal variance should be less than the maximum variance.

For back valued transactions, the system applies the rate on the basis of the exchange rate history. The variance will be based on the rate prevailing at that time.

Account Preferences

As part of specifying the account preferences, you can indicate the following:

Track receivable Auto Liquidation

Check this box to indicate that the receivables should be tracked during auto liquidation.

Liquidate Back Valued Schedules

Check this box to indicate that the schedules with a due date less than the system date should be liquidated on the initiation of back valued lease account.

Special Interest Accrual

Check this box to indicate that the accrual computation should be based on formula specified for a component. Otherwise, interest accrual will be done based on the number of days in the schedule.

Back Period Entry Allowed

Check this box to indicate that the lease account should be allowed to process transactions with a value date less than the current system date.

Interest Statement

Check this box to indicate that the interest statement should be generated for the account.

Product for Limits

Check this box to indicate that the product is for limits. If you check this option, the product will be available for limits linkage during line creation.

Partial Block Release

Check this box to indicate whether the partial release of term deposit should be done as part of loan repayment.

Schedule Basis

You should also specify the schedule basis for the rolled over lease. The new lease can inherit the schedules from the lease product or you can apply the schedules maintained for the original loan itself.

Liquidation

Liquidation preferences include the following:

Liquidation Mode

Indicate the mode of liquidation that you are maintaining. You can select one of the following options:

- Manual
- Auto
- Component

The default value for liquidation mode is 'Manual'. At the end of the day, liquidation will be done according to the specified mode.

Allow Partial Liquidation

In case of insufficient funds, check this box to indicate that the partial liquidation should be done automatically to the extent of funds available in the account you are maintaining. However, if this check box is not selected, the schedule amount due will not be liquidated if sufficient funds are not available in the account.

Reset Retry Count for Reversed Auto Liquidation

If you have maintained a limit on the number of retries for auto liquidation, this option will reset the retries count to zero during reversal of auto liquidation. This will be applicable from the date of reversal of payment. Hence, the system will once again attempt auto liquidation till the number of retries allowed. The system will update the status of the reversed payment to 'Unprocessed' after which it again attempts auto liquidation.

Retries Auto Liquidation Days

Capture the number of working days for which the system should attempt auto liquidation. The number of retries per day will depend on the configuration maintained for the 'Liquidation Batch Process' - during BOD, EOD or both. For instance, if the batch is configured for both EOD and BOD, and the number of retry days is '1', then, auto liquidation is attempted twice on the same day i.e. once during BOD and another retry at EOD.

Retries for Advice

Specify number of times you want to retry generation of advice. The number of retries should be less than 'Retries Auto Liquidation Days'. When auto liquidation fails and advice retry count is reached, the system generates a failure advice and sends it to the customer to initiate an appropriate action for the successful execution of the advice.

Tenor

Specify the following under Tenor in the screen:

Minimum Tenor

Specify the minimum amount of time that the customer can take to decide on the 'rate plan' and intimate the bank about the decision.

Maximum Tenor

Specify the maximum amount of time that the customer can take to decide on the 'rate plan' and intimate the bank about the decision.

Unit

Select the unit for the rate plan tenor from the drop-down list. The following options are available for selection:

- Monthly
- Yearly

4.1.4.2 Holiday Preferences Tab

The value date/maturity date of a contract might fall on a holiday defined for branch or on a holiday specified for the currency involved in the contract.

You need to specify the following holiday parameters, which has to be considered for holiday handling:

The screenshot shows the 'Preferences' dialog box with the 'Holiday Preferences' tab selected. The 'Product Code' and 'Description' fields are at the top. Below them are tabs for 'Account Preferences', 'Leasing Preferences', and 'Holiday Preferences'. The 'Holiday Treatment for Disbursement / Payment Schedules' section contains several options: 'Ad hoc Treatment Required' (checkbox), 'Ignore Holidays' (checkbox), 'Move Across Month' (checkbox), 'Cascade Schedules' (checkbox), 'Include Branch Holiday' (checkbox), 'Use Local Currency' (checkbox), 'Schedule Movement' (checkbox), 'Move Forward' (radio button), and 'Move Backward' (radio button). The 'Holiday Check' dropdown is set to 'Local'. Below these are two empty tables: 'Holiday Period' and 'Authorization Rekey'. The 'Holiday Period' table has a header row with 'Holiday Period' and a checkbox. The 'Authorization Rekey' table has a header row with 'Field Name' and a checkbox. At the bottom right are 'Ok' and 'Exit' buttons.

Holiday Treatment for All Schedules

The schedule date of a contract might fall on a local holiday defined for your branch or on a holiday specified for the currency involved in the contract.

You need to specify the following holiday parameters, which has to be considered for holiday handling:

Adhoc Treatment Required

Check this option to allow the movement of due dates of the schedules that fall on the newly declared holidays. This option is enabled only if the options, Ignore Holidays parameter and the Cascade Schedules parameter are not checked at the product level.

Move Across Month

Check this box to indicate that the schedule date falling on a holiday should be allowed to cross over into next/previous month.

If you have specified to move the schedule date of a lease falling due on a holiday, either to the next or previous working day and the movement crosses over into a different month, then this option will determine whether the movement should be allowed or not.

Ignore Holidays

Check this box to indicate that the holidays should be ignored while fixing schedule date. In such a case, if a schedule date falls on a holiday, the automatic processing of such a schedule is determined by your holiday handling specifications for automatic processes, as defined in the 'Branch Parameters' screen.

Cascade Schedules

Check this box to indicate that the schedule should be cascaded to all the other schedules fall on holidays. Hence, when you move a cascaded schedule which falls due on a holiday to the next or previous working day (based on the 'Branch Parameters'), the movement happens to other schedules too.

If not selected, only the affected schedule will be moved to the previous or next working day, as the case may be, and other schedules will remain unaffected.

However, when you cascade schedules, the last schedule (at maturity) will be liquidated on the original date itself and will not be changed like the interim schedules. Hence, for this particular schedule, the interest days may vary from that of the previous schedules.

Include Branch Holiday

Check this box to indicate that the branch holiday should be considered for schedule date.

Indicate the type of movement of the schedule that you are maintaining. You can select one of the following options:

- Move Forward: Indicates that the schedule date falling due on a holiday will be moved forward to the next working day.
- Move Backward: Indicates that the schedule date falling due on a holiday will be moved backward to the previous working day.

However, if you opt to ignore the holidays and do not select the 'Move Across Months' option, the system ignores the holidays and the due will be scheduled on the holiday itself.

Holiday Check

Select the type of holiday to be considered for schedule date from the adjoining drop-down list. This list displays the following values:

- Currency
- Local
- Both

Holiday Currency

Specify the currency based on which holiday check needs to be done for leases under this product. Input to this field will be mandatory if you have indicated 'Currency' in the 'Holiday Check' field. The adjoining option list displays all valid currency codes maintained in the system. You can select the appropriate one.

Auth Re-key Fields

As a cross-checking mechanism to ensure that you are invoking the right lease for authorization, you can specify that the values of certain fields should be entered, before the other details are displayed. The complete details of the lease will be displayed only after the values to these fields are entered. This is called the re-key option. The fields for which the values have to be given are called the re-key fields.

You can specify the values of a lease that the authorizer is supposed to key-in before authorizing the same.

You can select the fields from the option list provided. If no re-key fields have been defined, the details of the loan will be displayed immediately once the authorizer calls the loan for authorization.

The re-key option also serves as a means of ensuring the accuracy of the data captured.

4.1.4.3 Leasing Preferences Tab

The leasing preferences include the following:

Lease Payment Mode

Select the mode of payment of the lease from the adjoining drop-down list. This list displays the following values:

- Advance: The payment is made in the beginning of the schedule.
- Arrears: The payment is made in the end of the schedule.

Residual Value Basis

Residual amount is the price at which a lessee can buy the asset at the end of the lease. Select the basis of residual amount from the adjoining drop-down list. This list displays the following values:

- Percentage of asset amount
- Flat amount
- Percentage of lease amount

Using the aforementioned basis the system calculates the residual amount during the processing of contract. The value computed by the system can be altered while account booking.

Residual Auto Liquidate

Check this box to indicate that the residual amount is liquidated automatically.

Interest Subsidy Allowed

Check this box to indicate that the subsidy is allowed for interest rate. The system will process the EMI computation based on the subsidized rate.

Note

If this option is selected at the product level, then there must be at least one more interest component with 'Include in EMI' checked at the Product - Component level. Interest rate subsidy, is not applicable for operational lease

Residual Subsidy Allowed

Check this box to indicate that the subsidized residual amount will be used while liquidating the residual value. You can specify the subsidized residual amount at the account level.

Lease Asset Required

Indicate the preference of customer while booking a lease. You can select one of the following options:

- Lease with Asset: In this lease the asset will be associated with the lease account.
- Lease without Asset: In this lease the asset will not be associated with the lease account. But for financial leasing, you can buy the asset with the residual value as asset value at the end of the lease.

Note

At the time of closure of lease account through 'Close' operation, you can choose a different FA product other than the one already linked at product level.

Fixed Asset Product Code

Specify a valid FA product code that should be created when a lease account which has no asset associated with it, is closed. This adjoining option list displays all valid FA products maintained in the system. You can choose the appropriate one.

Prepayment of Lease

The following are the preferences based on which prepayment of amortized loan should be processed:

Recomputation Basis

Select the basis of re-computation of lease for the prepayment of the lease from the adjoining drop-down list. This list displays the following values:

- Recalculate Instalment Amount: In this case the tenor remains constant.
- Change Tenor: Here, the tenor is recomputed while the instalment remains constant.

Prepayment Effective From

Select the start of lease prepayment from the adjoining drop-down list. This list displays the following values:

- Next Instalment

The default value of lease prepayment is 'Next Instalment'.

Prepayment Equated Monthly Installment Type

Select the type of Equated Monthly Installment (EMI) prepayment from the adjoining drop-down list. This list displays the following values:

- Single Instalment: A single instalment is computed using the future rates.
- Multiple Instalment: Multiple EMIs are defined if a future rate change is known upfront.

Minimum Equated Monthly Installment Amount

Specify the minimum amount that has to be paid after recomputing the Equated Monthly Installment (EMI). The recalculated EMI after prepayment should be equal to or greater than this amount.

Equated Monthly Installment Currency

Specify the currency in which the minimum Equated Monthly Installment (EMI) amount should be paid.

Disbursement Mode

Indicate the mode of principal disbursement that you are maintaining. You can select one of the following options:

- Manual: You can manually disburse the lease using 'Disbursement' screen. Here, disbursement happens on demand.
- Auto: The system automatically disburses the lease during a batch process according to the schedules maintained. In this case, disbursement happens based on the disbursement schedule maintained for the product. This is defined in the 'Components' tab. By default, the system does an auto disbursal.

Note

This disbursement mode is only applicable for Financial Leasing.

For details, refer the 'Making Manual Disbursements' chapter of this User Manual.

4.1.5 Specifying Components

You have already maintained the components of the product in the 'Main' tab of the 'Product' screen. The features of the components are defined in the 'Components' tab of the screen.

Note that the components defined in the 'Main' tab are displayed in the form of a list in the screen above. From the component list, highlight a component and then go on to define the features for the selected component.

Component Details

The basic information for a component is specified here. This includes the following:

Component

The Components which are defined in Main Tab are available in Component list.

The Component which is selected in the list appears in Component field. For e.g. 'INSURANCE', 'MAIN_INT', 'PRINCIPAL' etc. Subsequently, you have to define the parameters for these components in the 'Component' tab of the screen.

Description

The system displays the description of the selected component, which is specified in the 'Main' tab.

Currency

Specify a valid currency that should be associated to the component. This adjoining option list displays all valid currencies maintained in the system. You can choose the appropriate one.

Calculation Type

This value is displayed based on the preference maintained in the 'Main' tab. However, you can change it. Select the method of the calculation which is to be associated with the component from the adjoining drop-down list. The list displays the following values:

- Formula with schedule (Component Type - Interest)
- Formula without schedule (Charge)
- Penal Interest
- Prepayment Penalty
- Discount
- Schedule without formula (Principal)
- No schedule No formula (Ad Hoc Charges)
- Penalty Charges

Note

'Penalty Charges' are calculated only once for a 'Penal Basis' schedule.

Include in EMI

Check this box to indicate that the selected component should be included in EMI calculation.

Main Component

Check this box to designate a component as the 'Main' Interest component. If you enable the 'Main Component' option for a particular component, the system treats this component as the main component and also uses this component for calculating EMI.

The default value of main component is 'MAIN_INT'.

Component Type

Specify a valid type of the component. This adjoining option list displays all valid types maintained in the system. You can choose the appropriate one.

A component can be of one of the following types:

- Charge
- Tax
- Insurance
- Interest

Note

You can not associate 'PRINCIPAL' component with a particular type.

Liquidation Mode

You can specify the mode of liquidation of the component from the drop-down list. The following options are available for selection:

- Auto
- Manual

Note

This is applicable only if 'Liquidation mode' is selected as 'Component' at the product preference level.

Component Attributes

The component attributes include the following:

Special Component

Check this box to indicate the component as a 'Special Component'. You can specify the special amount for the special component at the lease account level.

In Operational leasing, for the main interest component, the default value of 'Special Component' field is 'checked'.

Penal Basis

Specify the basis component on which the penalty is computed.

Periodicity

Select the periodicity of the component from the adjoining drop-down list. The list displays the following values:

- Daily
- Periodic

If you choose the periodicity as 'Daily', any changes to UDE and SDE values will result in recalculation of the component. The recalculation happens as and when a change in value occurs. If maintained as 'Periodic', the values and calculations of the elements will be refreshed on the last day of the period.

Formula Type

Select the type of the formula to be used for calculating the component from the adjoining drop-down list. The list displays the following values:

- User Defined: This can also include a combination of standard formulae for different schedules of the component or can have a completely user defined formula.
- Standard
 - Simple
 - Amort-Payment in Advance
 - Amort –Payment in Arrears
 - Amortized Operational

Note

For a financial lease, the default value of the formula type is 'Amort-Payment in Arrears'. If the payment mode is changed to advance, then you have to select the formula type 'Amort-Payment in Advance'.

Rate to Use

Specify a valid UDE rate that should be used in computing the standard formula. This adjoining option list displays all valid UDE rates maintained in the system. You can choose the appropriate one.

Basis Element

Specify a valid component that should be used in computing the standard formula. This adjoining option list displays all valid components maintained in the system. You can choose the appropriate one.

For interest and charges, this is applicable if 'Formula Type' is 'Standard' and this is not applicable if 'Formula Type' is 'User Defined'. For 'Principal' component, this is not applicable.

Balance Type

Indicate the type of balance that you are maintaining. You can select one of the following options:

- Debit
- Credit

Component Defaults

The following are the component defaults:

Days in Month

Select the number of days in a month for interest computation from the adjoining drop-down list. This list displays the following values:

- 30 (Euro): In this case, 30 days is considered for all months including February, irrespective of leap or non-leap year
- 30 (US): This means that only 30 days is to be considered for interest calculation for all months except February where the actual number of days is considered i.e. 28 or 29 depending on leap or non-leap year.
- Actual: This implies that the actual number of days is considered for calculation. For instance, 31 days in January, 28 days in February (for a non-leap year), 29 days in February (for a leap year) and so on

Days in Year

Select the number of days in a year for interest computation from the adjoining drop-down list. This list displays the following values:

- 360: This means that only 360 days will be considered irrespective of the actual number of calendar days.
- 365: In this case, leap and non leap year will be 365 .
- Actual: In this case, leap year will be 366 and non leap year will be 365.

Note

For EMI computation, the number of days in month/year is always 30/360.

Grace Days

Specify the number of days available without penalty after the due date. You have to repay the lease within the grace days to avoid the penalty.

Verify Funds

Check this box to indicate that the availability of funds in the customer account should be verified during liquidation.

Interest Method

Check this box to indicate that the interest method should be used for the selected component.

IRR Applicable

Check this box to indicate that the selected component should be considered for Internal Rate of Return (IRR) calculation. This option is applicable to interest, charge and insurance components.

If a charge component is to be considered for IRR, the charge will be accrued using the FACR (Upfront Fee Accrual) batch.

The following components cannot be considered for IRR calculation:

- Off-balance sheet component
- Provision component

If you check this option, then you have to check the 'Accrual Required' option.

For bearing type of component formula, you can check this option only if the 'Accrual Required' option is checked.

For discounted or true discounted types of component formula, this option will be enabled irrespective of the whether the 'Accrual Required' option is checked or not. If this option is checked and 'Accrual Required' is not, the discounted component will be considered as a part of the total discount to be accrued for Net Present Value (NPV) computation. If both 'Accrual Required' and 'IRR Applicable' are checked, then discounted interest will be considered for IRR computation.

Accruals/Provisioning/Interest Payback

To perform accrual of the components, you have to capture the following details:

Required

Check this box to indicate that the component should be accrued.

Required check box should be checked for interest payback component.

Frequency

Select the frequency of accrual from the adjoining drop-down list. This list displays the following values:

- Daily
- Monthly
- Quarterly
- Half Yearly
- Yearly

The frequency for interest payback component should not be selected as daily.

Start Month

Select the starting month of accrual from the adjoining drop-down list. This list displays the following values:

- January
- February
- March
- April
- May
- June
- July
- August
- September
- October
- November
- December

If you set the accrual frequency as quarterly, half yearly or yearly, you have to specify the **month** in which the *first* accrual has to begin, besides the date.

Start Date

Specify the starting date of accrual.

Start month and start date are not applicable for interest payback component if the component type is Interest Payback.

Prepayment Threshold

This includes the threshold amount and currency, explained below:

Amount

Specify the minimum limit for allowing prepayment of schedules. If the residual amount after prepayment against a schedule is less than the threshold amount you specify here, the system will disallow the prepayment.

Currency

Specify a valid currency in which the threshold amount should be expressed. This adjoining option list displays all valid currencies maintained in the system. You can choose the appropriate one.

4.1.5.1 Defining Formula

To compute component value for a particular schedule, you have to define a formula. You can define any one of the two types of formulae:

- Book
- Intermediate

Book

Booked Formula refers to the formula used to compute a component value for a particular schedule. You can use intermediate formulae to create a 'Booked' formula. To create the formula, click 'Book' in the 'Component' tab of the screen. The following screen is displayed:

The screenshot shows the 'Book Formula' dialog box. It includes a title bar with 'Book Formula' and a close button. The main area contains several input fields: 'Formula Name', 'Compound Days', 'Compound Months', 'Compound Years', 'Due Date On', and 'Start Month'. On the right side, there are three dropdown menus: 'Amortization Basis Element' (set to 'Amortized'), 'Round Up/Down (decimal)', and 'Rounding Factor(decimal)'. Below these fields is an 'Expression' section with a 'Go' button and a table with columns: Line, Condition, Result, Condition, and Form Type. The table is currently empty. At the bottom right, there are 'Ok' and 'Exit' buttons.

The SDEs available will be shown in the Condition Builder. The Booked formula so created will be linked to a schedule.

These are some of the examples of the formulae generated by the system on its own by choosing the formula type and the basis elements.

- Simple -
@SIMPLE(PRINCIPAL_EXPECTED,(INTEREST_RATE),DAYS,YEAR,COMPOUND_VALUE)
- Amortized Reducing -
@AMORT_RED(PRINCIPAL_EXPECTED,(INTEREST_RATE),DAYS,YEAR)
- Discounting -
@DISCOUNTED(PRINCIPAL_EXPECTED,(INTEREST_RATE),DAYS,YEAR)
- Amortised Rule 78 -
@AMORT_78(PRINCIPAL_EXPECTED,(INTEREST_RATE),DAYS,YEAR)
- True Discounted -
@TRUE_DISC(PRINCIPAL_EXPECTED,(INTEREST_RATE),DAYS,YEAR)
- Amort-Payment in Advance -
@AMORT_ADV(CAPITAL_AMOUNT,(INTEREST_RATE),DAYS,YEAR,RESIDUAL_AMOUNT)
- Amort payment in Arrears -
@AMORT_ARR(CAPITAL_AMOUNT,(INTEREST_RATE),DAYS,YEAR,RESIDUAL_AMOUNT)
- Amortized Operational
@AMORT_OPR(CAPITAL_AMOUNT,RESIDUAL_AMOUNT,NO_OF_PERIODS)

The parameters required to create a 'Booked' formula is similar to the ones explained for an Intermediate formula.

Amortized

Check this box to indicate that the schedules of the component should be amortized.

Amort Basis Element

If you opt to Amortize the schedules of the component, you have to identify the element based on which the component is amortized. For example, if it is deposit interest, the amortization basis would be 'Principal'. The components are available in the option list provided.

Intermediate

Intermediate Formulae are used as building blocks for more complex formulae. An intermediate formula is used to create a Book formula as an intermediate step. It will not be associated directly to any schedule.

To define an intermediate formula, click 'Intermediate' in the 'Components' tab of the screen. The 'Intermediate Formula - Expression Builder' screen is displayed.

The screenshot shows the 'Intermediate Formula' window. At the top, there is a navigation bar with '< 1 of 1 >'. Below it are input fields for 'Formula Name', 'Compound Days', 'Compound Months', and 'Compound Years'. To the right are two drop-down menus: 'Round Up/Down (decimal)' and 'Rounding Factor(decimal)'. Below these is an 'Expression' section with a 'Go' button and a table with columns: Line, Condition, Result, Condition, Form Type. The table is currently empty. At the bottom right are 'Ok' and 'Exit' buttons.

Formula Name

Specify a suitable name to identify the formula that you are defining. After you specify the name you can define the characteristics of the formula in the subsequent fields. You have to use the name captured here to associate a formula with a schedule. The name can comprise of a maximum of 27 alphanumeric characters.

Round Up/Down (Decimal)

If you want to round off the results of an intermediate formula, you can indicate whether the result should be rounded up or rounded down by choosing one of the following values from the drop-down list:

- Up
- Down

Compound Days/Months/Years

If you want to compound the result obtained for the intermediate formula, you have to specify the frequency for compounding the calculated interest.

The frequency can be in terms of:

- Days
- Months

- Years

If you do not specify the compound days, months or years, it means that compounding is not applicable

Rounding Factor

Specify the precision value if the number is to be rounded

It is mandatory for you to specify the precision value if you have maintained the rounding parameter.

Compound Days

If you want to compound the result obtained for the intermediate formula, you have to specify the frequency for compounding the calculated interest. The frequency can be in terms of days.

Compound Months


If you want to compound the result obtained for an intermediate formula, you have to specify the frequency for compounding the calculated interest. The frequency can be in terms of months.

Compound Years

If you want to compound the result obtained for an intermediate formula, you have to specify the frequency for compounding the calculated interest. The frequency can be in terms of years.

Condition and Result

A formula or calculation logic is built in the form of expressions where each expression consists of a 'Condition' (optional) and a 'Result'. There is no limit to the number of expressions in a formula. For each condition, assign a unique sequence number/formula number. The conditions are evaluated based on this number. To define a condition, click on 'Condition' in the screen above. The following screen is displayed:



In this screen, you can use the elements, operators, and logical operators to build a condition.

Although you can define multiple expressions for a component, if a given condition is satisfied, subsequent conditions are not evaluated. Thus, depending on the condition of the expression that is satisfied, the corresponding formula result is picked up for component value computation. Therefore, you have the flexibility to define computation logic for each component of the product.

The result of the formula may be used as an intermediate step in other formulae.

Schedule

In the 'Component' section of the screen, you need to maintain the applicable schedule details for each component:

Sequence Number

Specify the sequence number to determine the order in which the individual schedule should be applied on a component. You can define more than one schedule to a component.

Type

Select the type of schedule from the adjoining drop-down list. This list displays the following values:

- **Payment:** This type of schedule is used for the components Principal, Interest, Charge and Insurance.
- **Disbursement:** This type of schedule is only used for Principal component under financial leasing.
- **Rate Revision schedules:** This will capture the schedule at which the rates applicable to the component should be revised. This type of schedule is used for the interest, charge and insurance components.

Start Reference

Select the reference to arrive at the due date of the schedule from the adjoining drop-down list. This list displays the following values:

- **Calendar:** If you select this option, you should also specify the 'Start Date' for the schedule. For example, if an account is created on 15th Sept with a 'Monthly' schedule frequency and the Start Date is 1st, then the schedule due dates would be 1st Oct, 1st Nov and so on.
- **Value Date:** If you select value date, the schedule due dates will be based on the Value Date of the account. Here, the value date and start date is the same. For instance, if an account is created on 15th Sept and the schedule frequency is 'Monthly', then the schedule due date would be 15th October, 15th Nov and so on.

For a component, you can define schedules based on both value date and calendar date.

Frequency Unit

Select the unit of the schedule from the adjoining drop-down list. This list displays the following values:

- Daily
- Weekly
- Monthly
- Quarterly
- Half Yearly
- Yearly

If the schedule unit is 'Weekly', you should also capture the 'Start Day'. Similarly, for units 'Quarterly', 'Half Yearly' and 'Yearly', you should also specify the 'Start Month'.

Frequency

Specify the multiplier that should be multiplied with the frequency unit to derive the non-standard frequency unit. This is used in combination with 'Unit' explained above, to define non-standard frequencies. For instance, a 'Monthly' unit and frequency 2 implies that the schedule is bi-monthly (occurring every two months).

Start Day

Select the starting day of the schedule from the adjoining drop-down list, if the schedule unit is 'Weekly'. This list displays the following values:

- Sunday
- Monday
- Tuesday
- Wednesday
- Thursday
- Friday
- Saturday

Start Month

Select the starting month of the schedule from the adjoining drop-down list, if the schedule unit is one of the following:

- Quarterly
- Half Yearly
- Yearly

The drop-down box lists the months in a year.

Start Date

Specify a value between 1 and 31. This is applicable if the schedule unit is 'Monthly'

Formula

Specify a valid formula that should be used for calculating the component value. This adjoining option list displays all valid formulae maintained in the system. You can choose the appropriate one.

Number of schedules

Specify the number of times a schedule frequency should recur. For example, a 12 monthly schedule would have a 'Monthly' unit and number of schedules as 12.

4.1.6 Specifying Notices and Statements

Just as you define components that should become a part of the product, so also you can associate Notices and account statement with a product.

The actual communication/correspondence, however, is handled by the Messaging Module of Oracle FLEXCUBE. Click 'Notices and Statements' button in the 'Product' screen.

In this screen, you need to maintain the preferences for Billing Notices, Delinquency Notices, Rate Revision Notice, Direct Debit Notice and Statements. Also, you can associate multiple formats for the generation of notices and statements. The selection of a particular format is based on the condition.

Rule Number

You can assign a unique number for each rule/condition that is being maintained for notice and statement generation.

Condition

Define the conditions/rules for notice and statement generation. The system will evaluate the conditions and based on the one that is satisfied, the corresponding advice format is selected for notice/statement generation.

To maintain a condition, click 'Condition' button in the screen above. The 'Condition Builder' is displayed.

For details on building a condition using the options available in the screen, refer the section titled 'Defining UDE Rules' in the 'Maintenances and Operations' chapter of this User Manual.

Number of Days

The Number of days indicates the period before the due date, when the system starts sending the Billing/Delinquency notices to customers.

This period is defined as a specific number of days and will begin before the date the repayment becomes due.

Format

For the condition defined, select the format in which the advice should be generated. The system will select the specific format of the message type when the condition maintained evaluates favorably. Frequency Days

Specify the frequency (in days) for generation of Delinquency Notices. The first notice is sent on the basis of the 'Num Days' maintained. For instance, if the 'Num Days' is four and the

payment due date is 4th April 2004, the first notice will be sent on 31st March '04 (4 days before due date). Subsequent generation of the same notice is based on the frequency days maintained. If the 'Frequency Days' is '2', the second notice will be sent on 2nd April '04 i.e. the notice is sent once in two days only.

Message Type

For the condition defined, select the format in which the advice should be generated. The system will select the specific format of the message type when the condition maintained evaluates favorably.

Liquidation Frequency Days

Specify the frequency (in days) for generation of Delinquency Notices. The first notice is sent on the basis of the 'Num Days' maintained. For instance, if the 'Num Days' is four and the payment due date is 4th April 2004, the first notice will be sent on 31st March '04 (4 days before due date). Subsequent generation of the same notice is based on the frequency days maintained. If the 'Frequency Days' is '2', the second notice will be sent on 2nd April '04 i.e. the notice is sent once in two days only.

The following information is applicable to Statement generation:

Frequency

Indicate the frequency in which the Statements have to be generated. The available options:

- Daily
- Monthly
- Quarterly
- Half Yearly
- Yearly

Frequency Days

The frequency captured here is used to get the next date for statement generation subsequent to the first statement. This will be used in combination with the 'Frequency' explained above.

Start Date

The date entered here is used as a reference to start generation of the statement

Message Type

Specify the type of Statement that should be generated. Statements are of the following types:

- Interest Statements
- Loan Statements

Generic Notice

You can maintain the following details to generate a notice.

Notice ID

Select the notice type of the rate plan from the list of options.

Rule Number

Specify the unique number for the rule maintained for notice.

Condition

Specify the condition for notice generation. The system will evaluate the conditions and based on the one that is satisfied, the corresponding advice format is selected for notice.

Click 'Condition' button to maintain a condition in 'Product' screen. The 'Condition Builder' is displayed.

Format

Specify the format of the advice to be generated.

Tenor

Specify the tenor at which the notice has to be generated.

Number of Days

Specify the number of days required to intimate the customer in advance about the UDE rate change period.

Frequency

Specify the frequency in which the notice has to be generated.

Transaction Code

Specify the identifier code of the transaction.

Interest Rate Revision within the Rate Revision Period

The Rate Revision Notice section allows you to maintain the number of days for the generation of the advice, prior to the scheduled date of rate revision. During End of Day if the notification date is less than or equal to schedule date, a Rate Revision Advice is generated.

The four different conditions for the rate revision will be handled in Oracle FLEXCUBE as follows:

- Condition 1: Once the interest revision date is reached, the system continues to use the same interest rate code, till the next revision date.
- Condition2: If the request for change in interest rate is received a few days before the scheduled revision date, the interest rate code of the lease account is changed by value dated amendment, with the effective date as the scheduled interest revision date. On the effective date, the system changes the rate code and picks up the new interest rate
- Condition 3: If the request is for a future dated prepayment of the lease account there is no change in the interest rate, the principal is changed depending on the prepaid amount and once the payment is available in the settlement account, you can liquidate the lease manually with the requested effective date.
An outstanding component breakup of prepayment penalty charges if applicable is sent to the customer.
- Condition4: If the request for interest rate revision is made much before the scheduled revision date, you can change the interest rate code of the lease account by value dated amendment with effective date as requested.

The rate revision will be applicable on the total principal outstanding amount.

4.1.7 Mapping Accounting Role to Product

You can define the accounting roles for a product in the 'Role to Head' button of the 'Consumer Lending Product' screen. A list of accounting roles that are applicable to the

product being maintained is provided. This list also includes the accounting roles that you have maintained for the module using the 'Accounting Role and Head Maintenance' screen.

The screenshot shows a software window titled "Role To Head Mapping". At the top, there are two input fields: "Product Code" and "Product Description". Below these is a section titled "Class Details" containing "Class Code" and "Class Description" input fields, and a "Default From Class" button. Underneath is another section titled "Role To Head Mapping" which features a table with columns: "Map Type" (with a checkbox), "Accounting Role", "Role Description", "Account Head", "Head Description", and "Rule". Above the table are navigation arrows, "1 Of 1", and a "Go" button. At the bottom right of the window are "Ok" and "Exit" buttons.

The following details are captured in this screen:

Class Code

Select a class code from the adjoining option list. The option list displays all the valid classes maintained in the system.

Click 'Default from Class' button to default the role to head mapping details for the selected class. You can select and modify the required role to head mapping details to suit the product you are defining. You can also define new role to head mapping by clicking add icon.

Map Type

The mapping between an accounting role and account head can be of the following types:

- Static: If the map type is static, you can link an accounting role to only one accounting/GL head (one to one mapping).
- User Defined: For a user defined map type, you can maintain multiple linkages under different conditions using a case-result rule structure (one to many accounting).

Accounting Role and Description

Accounting role is used to denote the accounting function of a GL or Account. To map an accounting role to an account head, select a valid accounting role from the option list provided. This list will display the roles available for the module.

Once you choose the accounting role, the description maintained for the role is also displayed in the adjacent field.

If you do not want to select a role from the option list, you can also create an accounting role for a product and specify a brief description for the same.

Note

The GLs (Account Heads) for the Dr/Cr Settlement Bridge Role will default as per your selection in the 'Branch Parameters' screen.


Account Head and Description

The account head identifies the GL or Account to which the accounting entries would be posted. Based on the type of accounting role you select (Asset, Liability etc.), the list of Account Heads (General Ledger heads) that are of the same type as that of the accounting role, becomes available in the option list provided. You can select an accounting head from this list and thus, create a role to head mapping. On selection of the Account Head, the description is also displayed in the adjacent field.

Click Add icon to create subsequent mappings for the product. If you would like to delete a role to head mapping, click Delete icon.

Rule

If the 'Map Type' is 'User Defined', you can create a case-result rule structure based on which the entries are posted to the appropriate account head. To create a rule, click 'Rule' in the 'Role to Head' tab of the product screen.



The screenshot shows a window titled "Role Mapping". At the top, there is a navigation bar with "Expression" and "1 Of 1" with navigation arrows and a "Go" button. Below this is a table with the following columns: "Line", "Condition", "Account Head", and "Condition". The table is currently empty. At the bottom right of the window, there are "Ok" and "Exit" buttons.

You can define multiple conditions and for each condition you can specify the resultant 'Account Head'. This way you can maintain one to many mappings between an accounting role and an account head. Depending on the condition that is evaluated favorably, the corresponding account head is used for posting the entries.

To build a condition, click on 'Condition' in the screen above. The 'Condition Builder' is displayed.

You can build the conditions using the elements (SDEs), operators and logical operators available in the screen above.

For details on building a condition using the options available in the screen, refer the section titled 'Defining UDE Rules' in the 'Maintenances and Operations' chapter of this User Manual.

Note

The system ensures that all accounting roles that are applicable for the Product and which have been used in the definition of the accounting entries are necessarily linked to an account head. If the mapping is not complete, an error message is displayed when you attempt to save the product.

4.1.7.1 Dynamic creation of accounting roles for a component

For each component you define for a product in the 'Main' tab, six accounting roles are dynamically created by the system. For example, if you have defined a component 'MAIN_INT', the following accounting roles are created:

- MAIN_INTINC -Component Income
- MAIN_INTEXP -Component Expense
- MAIN_INTRIA -Component Received in Advance
- MAIN_INTPAY -Component Payable
- MAIN_INTREC -Component Receivable
- MAIN_INTPIA -Component Paid in Advance

For a detailed list of Events, Advices, Accounting Roles and Amount Tags, refer 'Annexure 1' of this User Manual.

4.1.8 Specifying Account Status

Ideally, when setting up a product, you should identify all possible status that lease involving the product would move into.

A status can apply either to a lease installment or the entire lease account. Installment level status change preferences are maintained in the 'Component' tab of the screen.

For more details, refer the section titled 'Component Details' in this chapter

You can maintain account level status movement preferences the 'Account Status' button of the screen.

In this screen, you can specify the following:

Class Code

Select a class code from the adjoining option list. The option list displays all the valid classes maintained in the system.

Click 'Default from Class' button to default the account status details for the selected class. You can select and modify the required details to suit the product you are defining. You can also define new account status by clicking the '+' button.

- Define a status derivation rule to resolve a status
- Define accounting entries, advices etc. which need to be fired for a status
- Specify the liquidation order for a status
- Associate charges, if applicable, for a status
- Policies to be triggered for a status change

Status

When setting up a product, you should identify all possible statuses that lease involving the product would move into. By default, the 'NORM' (Normal) status is defined for the product. You can select the relevant status codes from the option list provided. The status codes defined through the 'Status Codes Maintenance' screen with 'Status Type' as 'Account' is available in this list.

When you select a status, the associated description is also displayed in the adjacent field.

Adversity Level

This signifies the adversity level of the status. The Status 'NORM' has an adversity level of '1' and is the most favorable. This is the default status for a lease.

Accrual Preference

For a status, you have to indicate the manner in which accounting entries should be posted when the lease moves to the status. The options are:

- Stop Accrual – accruals are frozen
- Reverse Accrual – accruals till date are reversed by transferring them to an expense GL
- Continue Accrual – accruals continue as in the previous status as per the Role to Head maintained for the status and as per the accounting entries defined

After you specify the status codes applicable for the product, you need to specify the manner in which the status movement should occur.

From Status and To Status

When you highlight a status from the list of status codes maintained for the product, the selected status becomes the 'From Status'

In the option list provided for the 'To Status', the status codes applicable for the product is displayed. Select the relevant status into which a loan should move from the 'From Status'.

Movement Type

You have to indicate the type of movement of a lease from the current status (From Status) to the next status (To Status). The movement can be:

- Automatic
- Manual
- Both

Movement Rule

You have to define the status derivation rule which will determine the movement of a lease from one status to the other. This is the condition based on which the status movement occurs. If a lease satisfies all the rules defined due to which it can move to several statuses at a time, it will identify the most adverse status and move to that status.

To define a derivation rule, click 'Condition' button in the screen above. The 'Condition Builder' is displayed.

The screenshot shows a 'Condition Builder' window with the following components:

- Fields:** A text input field.
- Condition:** A text input field.
- Element:** A dropdown menu.
- Logical Op:** A dropdown menu.
- Mathematical Op:** A dropdown menu.
- Operator:** A dropdown menu.
- Value:** A text input field.
- Buttons:** 'And', 'Or', 'Accept', 'Clear Condition', 'Ok', and 'Exit'.

You can build the conditions using the elements (SDEs), operators and logical operators provided in the screen above.

For details on building a condition using the options available in the screen, refer the section titled 'Defining UDE Rules' in the 'Maintenances and Operations' chapter of this User Manual.

Complete Pending Accruals


Check this box to indicate if the pending interest accruals need to be completed before the Account status changes. This is applicable only if Accrual Frequency is any one of the following:

- Monthly
- Quarterly
- Half yearly
- Yearly

This check box will not be enabled if Accrual Frequency in the 'Consumer Lending Product' screen is 'Daily'.

4.1.8.1 Specifying Liquidation Order

You can prioritize the liquidation of the various lease components at a status level. To maintain liquidation order of components, click 'Liquidation Order' button in the 'Account Status' screen – the following screen is displayed.



When a loan attains an adverse status, you may want to allot priority to the recovery of certain components. For example, you may want to recover the Principal first and then the Interest type of components.


The components maintained for the product are available in the option list provided. Select a component and then specify the order of liquidation for the component.

Click on Add icon to maintain the liquidation order for the next component

4.1.8.2 Specifying Accounting Preferences

You can specify accounting preferences at a status level. You may have a GL structure under which loans in 'Normal' status should report. You can maintain a different structure for lease

in other status. To do this, click 'Accounting Entries' in the 'Account Status' tab – the following screen is displayed:




Also, for a status, you may not want to change accounting roles but change only the accounts/GLs. The accounting roles will be the same. To achieve this, you can create a rule based 'Role to Head' mapping. The SDEs like 'Account Status' can be used to create the rule and if a lease satisfies the rule i.e. moves to the status maintained in the rule, the Account Head selected for the rule is used for posting the entries.

Refer the section titled 'Role to Head Tab for details on creating a 'Role to Head' mapping.

4.1.8.3 Specifying Advices

You can also specify the advices that should be generated when a status change occurs. For instance, when a lease moves from an 'ACTIVE' status to an 'OVERDUE' status, you can choose to send an advice to inform the customer of the status change and request for payment.

The advices can be maintained in the 'Product Event Advices Maintenance' screen - click 'Advices' in the 'Account Status' tab to invoke it.




You can associate advices at an event level also.

For more details on maintaining advice preferences, refer the 'Maintaining Event details' section of this User Manual.

4.1.8.4 Specifying Policy Preferences

Just as you associate policies at an installment level, you can also associate policies for a lease account status. To do this, click 'Policies' in the 'Account Status' tab of the product screen – the following screen is displayed:



Specify the following in this screen:

Policy Code

The policies defined in the 'User Policy' screen are available in the option list provided. Policies are used to handle special validations and operations on a loan.

Execution Type


You can associate a policy at one of the following points in time in a lease-event lifecycle:

- Before Event
- After Event
- Both

The policy gets executed appropriately

4.1.8.5 Associating Charges

Whenever a lease undergoes a status change, you can apply charge on the lease. You need to associate charge components at a status level. To do this, click 'Charges' in the 'Account Status' tab of the screen – the following screen is displayed:



The charge type of components defined for the product (in the 'Components' tab of the screen) are displayed in the option list. Select the component you wish to associate with the lease. The charge is applied when the lease moves to the status and is debited to the customer account.

4.1.8.6 Processing at Account Level

At the account level, when there is a change in the status, Oracle FLEXCUBE will first check if accrual is required for the components. When the accrual frequency for a component is not 'Daily', Oracle FLEXCUBE will validate if the installment status or the account status changes before accrual execution date. If it changes, Oracle FLEXCUBE will trigger catchup accrual for the component till the installment status and the account status change date. Subsequent to this, Oracle FLEXCUBE will process the installment status change and account status change.

- An installment status change will not change the next execution date of unprocessed ACCR events
- A status change is applicable for both manual and automatic account status
- If you delete an account level status change, it will delete the catch up accrual accounting entries also
- If you reverse an account level status change, it will reverse the catch up accrual accounting entries as well

4.1.8.7 Maintaining Ad Hoc Charge Components

A component of the type Ad hoc can be set up using 'Components' tab in the 'Consumer Lending Product' screen since ad hoc charges cannot be computed upfront or scheduled. Select the option in 'Calculation Type' as 'No Schedule No Formula'.

The screenshot displays the 'Components' window in Oracle FLEXCUBE. The window is divided into several sections:

- Class Code:** Fields for Class Code and Class Description, with a 'Default From Class' button.
- Component Details:** Fields for Component, Description, and Calculation Type (set to 'No Schedule No Formula'). Includes an 'Include in EMI' checkbox.
- Component Attributes:** Includes 'Special Component' checkbox, Penal Basis, Periodicity, Rate To Use, Basis Element, Balance Type (radio buttons for Debit and Credit), and Formula Type (set to 'Amortized Reducing').
- Component Defaults:** Fields for Days in Month and Days in Year (both set to 'Actual'), Grace Days, and Interest Method Default From Currency Definition.
- Accruals/Provisioning/Interest Payback:** Includes 'Main Component' checkbox, Currency, Component Type, 'Compound on overdue' checkbox, and Liquidation Mode (set to 'Auto').
- Prepayment Threshold:** Includes 'Required' checkbox, Frequency, Start Month, and Start Date.
- Schedule:** A table with columns: Sequence Number, Schedule type, Start Reference, Frequency Unit, Frequency, Start Day, Start Date, Start Month, Due Date On, Schedule Flag, No of Schedules, Capitalized, and Formula Name. The table is currently empty.

At the bottom of the window, there are 'Book Formulae' and 'Intermediate Formulae' tabs, and 'Ok' and 'Exit' buttons.

4.1.9 Specifying Events

A contract goes through different stages in its life cycle. In Oracle FLEXCUBE, the different stages a contract passes through in its life cycle are referred to as 'Events'.

At an event, typically, you would want to post the accounting entries to the appropriate account heads and generate the required advices. When setting up a product, you can define the accounting entries that have to be posted and the advices that have to be generated at the various events in the life cycle of accounts involving the product.

Therefore, for the required events you have to specify the Accounting entries, Charges, Policies and Advices. To do this, click 'Events' button in the 'Product' screen – the following screen is displayed.

The screenshot shows the 'Events' window with the following components:

- Product Code** and **Product Description** input fields.
- Class Details** section containing:
 - Class Code** input field with a **Default** button.
 - Class Description** input field.
- Events** section containing a table with columns **Event Code** and **Description**.
- Navigation controls above the table: **1 Of 1** and a **Go** button.
- Bottom menu bar: **Accounting Entries | Policies | Advices | Charges | Event Fields**.
- Bottom right buttons: **Ok** and **Exit**.

You can specify the following details:

Class Code

Select the class code from the adjoining option list. The list displays all the class codes maintained in the system.

Click 'Default' button to default the events maintained for the selected class. You can select the required events for the product you are defining. You can also define new events apart from the defaulted events.

Event Code and Description

These are the events for which the accounting entries, advices, policies and charges will be maintained, individually. The event codes applicable for the module are available in the option list provided. This list also includes user defined events set up for the module. Select the relevant events for the product from this list.

The description for the event chosen is also displayed

4.1.9.1 Defining Accounting Entries

To define accounting entries for an event, click 'Accounting Entries' in the 'Events' screen – the 'Accounting Entries' screen is displayed.

The screenshot shows the 'Accounting Entries' window. It contains two main sections: 'Accounting Rules' and 'Accounting Entry'. The 'Accounting Rules' section has a table with columns for 'Rule Number', 'Condition', and 'Condition'. The 'Accounting Entry' section has a table with columns for 'Entry Pair Number', 'Accounting Role', 'Amount Tag', 'Debit Credit Indicator', 'Transaction Code', and 'Netting Indicator'. Both sections have a 'Go' button and navigation arrows. At the bottom right, there are 'Ok' and 'Exit' buttons.

With the Rule definition builder, you can maintain different set of accounting entries for different conditions.

Rule Number

Every rule/condition you define for a product should be assigned a unique number. The rule number can consist of a maximum of 5 digits

Case

You can use the 'Condition Builder' to define a rule. Click on 'Condition' in the above screen to invoke it.

The screenshot shows the 'Condition Builder' window. It has several input fields and buttons. On the left, there are 'Fields', 'Condition', 'Element', 'Logical Op', and 'Mathematical Op' fields. On the right, there is an 'Operator' dropdown menu and a 'Value' field. Below the 'Value' field are buttons for 'And', 'Or', 'Accept', and 'Clear Condition'. At the bottom right, there are 'Ok' and 'Exit' buttons.

You can define a rule using the SDEs like Tenor, Customer Risk Category and other UDEs.

If you do not specify a rule/condition, the accounting entries become applicable to all conditions.

Accounting Role

Select the accounting role that should be used at the event. The option list displays all the accounting roles specified for the product in the 'Role To Head' tab of the 'Consumer Lending Product' screen. Select the role appropriate for the event.

Amount Tag

Specify the amount tag applicable for the Accounting Role. An amount tag identifies the amount/value that is actually due for a component. Depending on the components defined for the product, the system dynamically creates a set of amount tags. For instance, if the component is 'MAIN_INT', the following amount tags are automatically created:

- MAIN_INT_RESD - Component Amount Residual
- MAIN_INT_ADJ - Component Amount Adjustment
- MAIN_INT_LIQD - Component Amount Liquidated
- MAIN_INT_CAP - Component Amount Capitalized
- MAIN_INT_ACCR - Component Amount Accrued
- MAIN_INT_DLIQ-Component Amount Paid against Due Schedules/future not-due schedules
- MAIN_INT_OLIQ-Component Amount Paid against Overdue Schedules

The '_DLIQ' and '_OLIQ' tags will be generated only for the events LIQD and ROLL.

Select the appropriate amount tag from this list

Debit or Credit

Here, you have to specify the type of accounting entry to be posted – the entry can be a debit entry or a credit entry.

Transaction Code

Every accounting entry in Oracle FLEXCUBE is associated with a Transaction Code that describes the nature of the entry. Specify the transaction code that should be used to post the accounting entry to the account head. You can group all similar transactions under a common transaction code. The transaction codes maintained in the 'Transaction Code Maintenance' screen are available in the option list provided.

Netting

Specify whether accounting entries should be netted at an event. You can net the accounting entries that are generated at an event by selecting 'Yes' from the drop down list. The system will then net the entries and show the resultant value in account statements. If you do not net, the entries will be shown separately in the statements.

MIS Head

An MIS Head indicates the manner in which the type of entry should be considered for profitability reporting purposes. This classification indicates the method in which the accounting entry will be reported in the profitability report. It could be one of the following:

- Balance
- Contingent Balance
- Income
- Expense

You can also link a product to an MIS Group if you do not want to define individual entities for the product.

Refer the section titled 'Associating an MIS Group with the product' in this chapter for more details.

Revaluation Required

Online Revaluation refers to revaluation done on transaction amounts during transaction posting, and not as part of an end-of-day process. The Revaluation profit /loss are booked to the Online 'Profit GL' or Online 'Loss GL' that you maintain for the GL being revalued.

You can opt for online revaluation by selecting the 'Reval Req'd' option.

Profit GL and Loss GL

If you have opted for online revaluation and the result of revaluation is a profit, the profit amount is credited to the Profit GL you select here. Similarly, if the result of revaluation is a loss, the loss amount is credited to the Loss GL you specify here.

Reval Txn Code

If you opt for online revaluation, you need to associate the transaction code to be used for booking revaluation entries. The system will use this transaction code to track the revaluation entries.

Holiday Treatment

Specify whether holiday treatment is applicable for processing accounting entries falling due on holidays. Select one of the following:

- Yes
- No

GAAP

Indicate the GAAP indicators for which the accounting entry is required for reporting under multi GAAP accounting. The adjoining option list shows all the GAAP indicators maintained in the system. Choose the appropriate one.

The system will then post entries into the specified books (GAAP indicators) during the different events that occur in the lifecycle of the lease. You can retrieve the balance for a certain component in an account in a specific status, for a given GAAP indicator, in a certain branch, reporting to a certain GL. The system will show the real and contingent balances accordingly.

Split Balance

Specify whether you need the balances to be split or not. If you check this option, the system will store the balance break-up for the specified GAAP indicators. You can then retrieve the balances separately for the different GAAP indicators to which accounting entries are posted for the lease.

If you need to move the balances from multiple/Single GLs, where the balances are currently lying, check this box. In such case the credit leg will be governed by the GLs from where component balances need to move, and not the GL maintained at the product level for the event.

Balance Check in Batch

Indicate whether the balance check is required for the batch operations/online processing.

The options available are:

- Reject – The transaction is rejected if there is insufficient fund to process the transaction.

- Delinquency Tracking – The transaction is processed. If you have specified delinquency tracking for the accounting entries, the tracking is done according to the parameters you have defined for the Delinquency Product.
- Force Debit – The transaction is processed. However, no delinquency tracking is done even if the account goes into overdraft.
- Partial Liquidation – The transaction is processed. If you have specified partial delinquency, the system liquidates upto the available amount and the delinquency tracking is done on the remaining amount only.

Delinquency Product

In case you have specified delinquency tracking for balance check type, you need to specify the delinquency product under which the entry is tracked. The option list displays all the delinquency product codes maintained in the Oracle FLEXCUBE. Select the appropriate from the option list.

Settlement


This field used to settle the amount. If it set as yes, while doing settlement system uses the Account used during amount settlement. If it is no it will use default account, which is mapped in role to head.

If you have selected the 'Accounting Role' as DR_SETTL_BRIDGE or CR_SETTL_BRIDGE in and if 'Settlement' box is checked then system looks at the default settlement accounts maintained in the Debit settlement Mode and Credit settlement mode. If 'Settlement' box is not checked then the system tries to arrive at the GL through Role to Head Mapping.

4.1.9.2 Specifying Advices for an Event

You can select the advices that should be triggered for various events. The selected advices are generated, once the product is authorized. These advices can be simple Debit /Credit advices when any payment or disbursement is made, Deal Slip advices, Rate Revision advices, Loan advices etc.

To specify the advices for an event, click 'Advices' button in the 'Events' screen of the 'Product Maintenance' screen – the following screen is displayed.



The following advice details have to be maintained in the screen:

Event Code

Code of the specified event is defaulted from the Event level.

Description

Description of the specified event is defaulted from the Event level.

Advices Details

The following advice details can be maintained here:

Advice Name

Specify a valid advice you want to trigger, from the adjoining option list. This option list displays advices applicable for the module.

Description

Description of the specified advice is defaulted here.

Generation Time

Authorization is defaulted as the generation time for all advices which need to be generated for a specified Event.

Suppress

Select 'Y' or 'N' from the adjoining drop-down list to either suppress or allow the generation of some advices.

Priority

Select the importance of the advice generation from the adjoining drop-down list. This list displays the following values:

- High
- Medium
- Low

Charges

Check this box if you want to collect charges for advice generation.


For a detailed list of Events, Advices, Accounting Roles and Amount Tags, refer 'Annexure A' of this User Manual.

4.1.9.3 Defining User Defined Policies

Policies are user defined validations that will be fired when any event is triggered. These can even be policies which govern the firing of an event under certain conditions.

For example, if an operation called payment is being done and the customer is paying an amount greater than his current overdue and one additional installment, you can associate a policy to disallow the payment. Therefore, you have to associate policies to an event.

Click on 'Policies' button in the 'Events' screen to define the policies that should be executed for an event.




You can select the appropriate policy from the option list provided. The policies defined in the 'User Policy' screen are available in this list. You should also specify the instance when the policy should be triggered for the event. The options are:

- Before Event
- After Event
- Both

4.1.9.4 Associating Charges

You can associate charges to an event. Linking a charge to an event implies calculating the value of the charge.

To associate charges, click 'Charges' button in the 'Event' screen.



The charge type of components defined for the product (in the 'Components' tab of the screen) are displayed in the option list. Select the component you wish to associate with the event.

4.1.9.5 Defining Event Fields

You can invoke the 'Event Fields' screen by clicking on the 'Event Fields' button on the 'Events' screen.

The screenshot shows a window titled 'Event Fields' with three sections for defining fields:

- Character Fields:** A table with columns 'Field Number', 'Field Name', and 'Description'. It includes a 'Go' button and navigation controls.
- Number Fields:** A table with columns 'Field Number', 'Field Name', and 'Description'. It includes a 'Go' button and navigation controls.
- Date Fields:** A table with columns 'Field Number', 'Field Name', and 'Description'. It includes a 'Go' button and navigation controls.

At the bottom right of the window, there are 'Ok' and 'Exit' buttons.

4.1.10 Maintaining Branch /Currency Restriction

The lease products created in the Head Office Bank (HOB) are available across all the branches subject to the branch restrictions maintained for the product. Likewise, you also restrict the products to select currencies. To achieve this, you can maintain a list of allowed/disallowed branches and currencies

Click on the 'Branch /Currency Restriction' button in the product screen.

The screenshot shows a software window titled "Branch and Currency Restriction". It features a top navigation bar with "Branch and Currency Restriction" and "Currency Balances" tabs. Below the navigation bar are input fields for "Product Code", "Description", "Class Code", and "Class Description". There are two radio button options: "Branch Restrictions" (with sub-options "Allowed" and "Disallowed") and "Currency Restrictions" (with sub-options "Allowed" and "Disallowed"). Below these are two data grids. The "Branch Restrictions" grid has columns for "Branch" and "Description". The "Currency Restrictions" grid has columns for "Currency Code", "Currency Description", and "Minimum Loan Am". Both grids show "1 Of 1" records. At the bottom right are "Ok" and "Exit" buttons.

The following details are captured here:

4.1.10.1 **Branch /Currency Restriction tab**

Under Branch and Currency Restrictions respectively, two columns are displayed.

- Allowed List
- Disallowed List

The allowed or disallowed column that is displayed would depend on the list type that you choose to maintain. For instance, if you choose to maintain an allowed list of branches, the column would display the branches that you can opt to allow.

In the Branch Restriction and Currency Restriction Section, click on the adjoining option list to invoke a list of bank codes and currencies codes respectively that you have maintained in your bank. Select an appropriate code.

Using the Add or Delete icons, you can add/delete a branch or currency from the corresponding allowed/disallowed column that you have maintained.

Note

When you create a product, it is, by default, available to all the branches of your bank, in all currencies, and for all customers unless restrictions are explicitly specified for the product.

Minimum Loan Amount

Specify the minimum amount for all the allowed currency maintained at the product level.

Maximum Loan Amount


Specify the maximum amount for all the allowed currency maintained at the product level.

Note

System checks the following:

- At the product level, if the minimum amount is less than the maximum amount
 - At the Lease Contract screen, if the amount financed falls in the range of minimum and maximum amount derived from product for the currency same as the lease currency
-

4.1.10.2 **Currency Balance Restriction Tab**



You can maintain the following currency balance details:

Currency Code

You can specify the transaction limit for a currency while defining currency restrictions for a product. Choose the currency code from the option list.

Residue Amount

Here, you have to capture the minimum amount by which, if a component of a schedule becomes overdue, the system will consider it as paid.

Negative Residue Amount

If the difference between the amount paid (COMPONENT_EXPECTED) and the amount due is less than the residue amount specified here, then the difference is treated as an income otherwise the transaction is rejected.

In the case of an income, the installment schedule is marked as completely settled/paid and the income is posted to the residual suspense GL. This triggers the event called 'RESD' (Residual) and the following entries are passed:

Accounting Role	Amount Tag	Dr/Cr
Lease Account	RESIDUAL_AMOUNT	Cr
Residual Suspense	RESIDUAL_AMOUNT	Dr

ATM Cash limit

Here, you can enter the maximum non- Cash transaction amount for the currency that you have defined. The ATM transaction amount cannot exceed the value given here.

Rounding Factor (EMI)

Specify the rounding factor if the EMI is to be rounded.

It is mandatory for you to specify the rounding factor if you have maintained the rounding parameter.

Round Up/Down

Indicate whether the EMI should be rounded up or down.

- Choose 'UP' in case you want to round the number to the next decimal value.
- Choose 'DOWN' if you want to truncate the number to the previous decimal value

The principal component of the EMI is adjusted based on the rounded EMI amount.

Numerator Method

Specify the day count method for the numerator for each currency applicable to the product. The following options are available in the drop-down list:

- Actual
- 30 Euro
- 30 US

Choose the appropriate one. This value will be used for calculation of the Net Present Value (NPV).

Denominator Method

Specify the day count method for the denominator for each currency applicable to the product. The following options are available in the drop-down list:

- 360
- 365

Choose the appropriate one. This value will be used for calculation of the Net Present Value (NPV).

4.1.11 Restricting Customer Category

Just as you can maintain a list of allowed/disallowed branches and currencies for a product, you can maintain a list of allowed/disallowed customer categories.

You can maintain several restrictions for each customer category.

The screenshot shows the 'Customer Category Restriction' window. It includes fields for Product Code, Product Description, Class Code, and Class Description. A 'Default From Class' button is present. The 'Customer Category Restriction' is set to 'Allowed'. Two data grids are shown: 'Category Restrictions' with columns for Customer Category and Description, and 'Customer Restrictions' with columns for Customer No, Description, and Allowed. The window has 'Ok' and 'Exit' buttons at the bottom right.

You can restrict customers from availing a product by maintaining an 'allowed' list or a 'disallowed' list of customer categories.

Only customer categories that are a part of an allowed list maintained for a product *can* avail the product. Likewise, customer categories that are part of a disallowed list *cannot* avail the product or service.

The allowed or disallowed column that you view depends on the list type that you choose to maintain. For instance, if you choose to maintain an allowed list, the column would display those customer categories that you choose to allow.

You can move a category to the allowed/disallowed column, using the Add or Delete icons.

4.1.11.1 **Allowing Access to Special Customers**

Depending on the customer restriction you specify – allowed or disallowed, you can further maintain a list of customers who are allowed (for a 'Disallowed' list) or specific customers who are not allowed to use the product (in the case of an 'Allowed' list). For example, you may disallow the customer category 'CORPORATES' from availing a certain lease product. However, you may want to allow 'Cavillieri and Barrett' (belonging to the category 'CORPORATES') to avail the product.

Select the name of the customer from the option list provided. The 'Customer Name' is displayed after you select the customer id.

If the selected customer belongs to a category which is 'Disallowed' for the product but you want to allow the customer, check the 'Allowed' option. Similarly, if the customer belongs to a category that is 'Allowed' but you want to disallow the customer, do not check the 'Allowed' option.

4.1.12 **Defining Product Fields**

Product Fields are additional fields that are available for use depending on the bank's requirement. You can define the Product Fields in the 'Product Fields' screen.

In the Product Field button of the screen, you can associate these custom fields with the product.

Product Fields

Product Code Product Description

Character Fields | Number Fields | Date Fields

Character Fields

◀ 1 Of 1 ▶ Go

Field Number	Field Name	Field Description
--------------	------------	-------------------

Ok Exit

The Product Fields are segregated based on the 'Field Type', into the following:

- Character Fields
- Number Fields
- Date Fields

When you select an UDF from the option list, the value is also displayed in the adjacent field.

4.1.13 Associating an MIS Group with the Product

You can associate MIS details with a product in the 'MIS' screen. Click 'MIS' button in the 'Product' screen to invoke it.


The screenshot shows the 'MIS Details' window. At the top, there are input fields for 'Product Code', 'MIS Group', and 'Pool Code'. To the right of the 'MIS Group' field is a button labeled 'Default From MIS Group'. Below these fields is a 'Cost Code' field with three lines of input. On the left side, there is a 'MIS Classes' section with a table. The table has two columns: 'MIS Class' and 'MIS Code'. Above the table is a navigation bar with '1 Of 1' and a 'Go' button. At the bottom right of the window are 'Ok' and 'Exit' buttons.

In this screen, you can associate an 'MIS Group' to which the product should be linked (if it is applicable; if not, you can define the individual entities under which the product should be reviewed).

To associate a group, check the 'Link Group' option. If a group is linked, the entities defined for the group will be displayed. Only the Transaction MIS Code will be applicable to a product. The specific MIS entity (in the form of an MIS Code) will be picked up by default only if you have defined them for the group. If not, you have to indicate the appropriate MIS code for each applicable MIS class.

4.1.14 Defining User Defined Fields

You can associate user defined fields to a product by using the 'User Defined Fields' screen. Click 'Fields' button in the Product screen to invoke it.




Here you can capture the following details:

Field Number

The system displays the field name.

4.2 Viewing Product Summary Details

You can view the summary of the products maintained in the system in the 'Product Summary' screen. You can invoke the 'Product Summary' screen by typing 'LESPRMNT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



The following details have to be captured in this screen:

Authorization Status

Select the status of authorization from the adjoining drop-down list. This list displays the following values:

- Authorized
- Unauthorized

Product Category

Specify a valid category that should be displayed. This adjoining option list displays all valid categories maintained in the system. You can choose the appropriate one. Hence, this module deals with leasing, you have to specify the category 'Leasing' in this field.

Lease Type

Select the type of lease from the adjoining drop-down list. This list displays the following values:

- Financial
- Operational

Record Status

Select the status of record from the adjoining drop-down list. This list displays the following values:

- Open
- Closed

Product Code

Specify a valid code that should be displayed. This adjoining option list displays all valid codes maintained in the system. You can choose the appropriate one.

Lease Payment Mode

Select the mode of paying the lease from the adjoining drop-down list. This list displays the following values:

- Advance
- Arrear

After specifying any or all of the aforementioned details, click 'Search' button to view the details of lease maintained in the system. The system displays all the available records based on the details specified in this screen.

You can double click on anyone of the displayed records to view the product detailed screen.

4.3 Processing EMI on Lease

The Equated Monthly Installment (EMI) is a fixed payment amount which is used to pay off both interest and principal each month. For the computation of EMI, the following formula should be defined in 'Book Formula'.

EMI Formula for Financial Lease

According to the payment type the formula for financial lease varies.

For Payment in Advance,

$$EMI = C$$

$$EMI = \frac{C - \frac{RV}{(1+I)^n}}{1 + \frac{1 - \frac{1}{(1+I)^{n-1}}}{I}}$$

Where:

- **C** = Capital = Amount Financed – Down Payment
- **RV** = Residual Value
- **I** = Periodic Rate of Interest
- **n** = Number of Periods

For Payment in Arrears,

$$EMI = I \times \frac{\left[C - \frac{RV}{(1+I)^n} \right]}{1 - \frac{1}{(1+I)^n}}$$

Where:

- **C** = Capital = Amount Financed – Down Payment
- **RV** = Residual Value
- **I** = Periodic Rate of Interest
- **n** = Number of Periods

EMI Formula for Operational Lease

EMI = Lease Amount/Tenor (no. of instalments)

Where:

Lease amount = Amount Financed – down payment

5. Account Creation

A contract is customer-specific. When you grant a lease to a customer, you enter into a contract.

Every time a lease is issued to a customer, it is not necessary to specify its general attributes, since a lease acquires the attributes defined, for the product it involves. You can change the general attributes for a lease at the time of processing a lease.

In addition to the general attributes, which a lease inherits from a product, there are the specific attributes, which have to be defined for it. They are:

- Customer details
- Lease Amount
- Lease Currency
- Repayment account for the lease

This chapter contains the following sections:

- [Section 5.1, "Lease Account Details"](#)
- [Section 5.2, "Saving and Authorising Mortgage/Commitment Account"](#)
- [Section 5.3, "Multilevel Authorization of a Contract"](#)
- [Section 5.4, "Viewing Lease Account Summary Details"](#)
- [Section 5.5, "Maintaining Events Dairy"](#)

5.1 Lease Account Details

This section contains the following topics:

- [Section 5.1.1, "Maintaining Lease Account Details"](#)
- [Section 5.1.2, "Main Tab"](#)
- [Section 5.1.3, "Account Details Tab"](#)
- [Section 5.1.4, "Default Tab"](#)
- [Section 5.1.5, "Checklist Tab"](#)
- [Section 5.1.6, "Fields Tab"](#)
- [Section 5.1.7, "Components Tab"](#)
- [Section 5.1.8, "Charges Tab"](#)
- [Section 5.1.9, "Linkages Tab"](#)
- [Section 5.1.10, "Advices Tab"](#)
- [Section 5.1.11, "Credit Score Tab"](#)
- [Section 5.1.12, "Capturing Additional Details for Leasing"](#)

5.1.1 Maintaining Lease Account Details

You can maintain the leasing account details using the 'Leasing Account Details' screen. You can invoke this screen by typing 'LEDACCDT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot displays the 'Leasing Account Details' application window. The window title is 'Leasing Account Details'. It features a top navigation bar with 'New' and 'Enter Query' buttons. Below this is a search area with fields for Branch, Account Number, Product, Product Category, Alternate Account Number, Derived Status, User Defined Status, and User Reference. A 'Go' button is present. The main area is divided into tabs: 'Main', 'Account Details', 'Default', 'Check List', 'Fields', 'Components', 'Charges', 'Linkages', 'Advice', and 'Credit Score'. The 'Account Details' tab is active, showing fields for Customer Id, Customer Name, Currency, Amount Financed, Net Principal, Down Payment, Residual Value Basis, Residual Value, Residual Amount, Subsidized Residual Amount, Value Date, Maturity Date, and Securitization status. There are also buttons for 'Payment Mode' (Default), 'Lease Type', 'Lease Payment Mode', 'Supplier id', 'Supplier Name', 'Subsidy Customer Id', and 'Subsidy Customer Name'. A 'Promotions' table is visible at the bottom right, with columns for Promotion Type, Promotion Id, Beneficiary, and Priority. The bottom status bar includes 'MIS | GL Balance | IRR Details | Events | Installment | SWIFT Message Details | Asset Values | Securitization History | Liquidation Order' and fields for 'Input By', 'Authorized By', 'Contract Status', and 'Authorized'. An 'Exit' button is in the bottom right corner.

You can specify the following generic details in the Account Details screen:

Branch

The system displays the Branch Code of the branch into which the user has logged in, for which the UDE values are maintained.

Account Number

Based on the leasing parameters that setup at the branch level, the account number would be either auto generated or would have to be captured in this field.

Product Code

Specify the product code for the lease account from the option list. Double click on a Product Code to select a particular code. The product codes are maintained in the Product Definition screen.

Click 'P' button to populate the Product Category, Value Date, Maturity Date based on the Product Code selected, the main screen will display all these values.

Alt Acc No

Specify the alternate account number in this field. It can be an account number in the existing system from which the account has migrated to Oracle FLEXCUBE.

User Defined Status

After you enter the account number, the system displays the status of the account in this field. This is based on the products status maintenance rules.

User Reference Number

A 16-digit User Reference Number is autogenerated and displayed here if the 'Auto Generate User Ref No' option is checked in the Branch Parameters. The format of the user reference number is BranchCode + ProductCode + Sequence number. You are allowed to modify the auto-generated User Ref No.

If the 'Auto Generate User Ref No' in Branch Parameters is not checked then the User Ref No will be blank by default and you have to specify it manually. Validations are done by the system not to save the account if an unsuppressed payment message is present which has the User Ref No as blank.

5.1.2 Main Tab

You can capture the main details of the leasing account in this tab.

The screenshot shows the 'Leasing Account Details' form. The top section contains fields for Branch, Account Number, Product, Product Category, Alternate Account Number, Derived Status, User Defined Status, and User Reference. Below this is a tabbed interface with 'Main' selected. The 'Account Details' section includes fields for Customer Id, Customer Name, Currency, Amount Financed, Net Principal, Down Payment, Residual Value Basis, Residual Value, Residual Amount, Subsidized Residual Amount, Value Date, Maturity Date, and Securitization status. The 'Payment Mode' section includes Lease Type, Lease Payment Mode, Supplier id, Supplier Name, Subsidy Customer Id, and Subsidy Customer Name. The 'Promotions' section is a table with columns for Promotion Type, Promotion Id, Beneficiary, and Priority. The bottom of the form has a status bar with fields for Input By, Authorized By, Contract Status, and a checkbox for Authorized. There are also navigation buttons like 'Go', 'Asset', and 'Financials'.

The following details regarding the leasing account are captured here:

Account Details

Amount Financed

Specify the total lease amount. On saving the transaction after entering all the required details in the system, the system validates the value of the transaction amount against the following:

- Product transaction limit
- User Input limit

If the transaction currency and the limit currency are different, then the system converts the amount financed to limit currency and checks if the same is in excess of the product transaction limit and user input limit. If this holds true, the system indicates the same with below override/error messages:

- Number of levels required for authorizing the transaction

- Transaction amount is in excess of the input limit of the user

Currency

Specify the currency of the lease.

Customer No

Specify the customer number.

Customer Name

The system displays the customer name.

Down Payment

Specify the total down payment for a lease account.

Note

The down payment should always be less than the amount financed.

Residual Value Basis

The system displays the residual value basis from the product code. The value computed by the system can be altered while account booking.

Residual Value

Specify the percentage of asset, percentage of lease or flat amount based on the residual value basis defined at the product.

Residual Amount

The system displays the residual amount after computing the percentage of asset or lease amount. In case of flat amount, residual value is copied to residual amount.

Note

Residual Amount should be less than the lease amount minus the down Payment.

Subsidy Customer Name

Specify the ID of the party who provides the subsidy for leasing.

Subsidy Customer Name

Specify the name of party who provides the subsidy for leasing. Based on this the system displays the settlement details for the subsidy components.

Value Date

Specify the value date for the lease account.

Maturity Date

Specify the maturity date for the lease account.

Securitization status

The system displays the securitization status. The status can be anyone of the following:

- Blank – Indicates account is not involved in securitization, that is it not part of the securitization pool
- Marked for securitized – Indicates loan account is part of securitization contract (on batch); however, the securitization batch is not executed yet.
- Securitized – Indicates the successful completion of batch process.

Lease Type

The system displays the type of lease.

Payment Mode

The system displays the mode of payment.

Account Statistics

The system displays the various balances for every component.

Supplier ID

Select the supplier or vendor ID from the option list.

Supplier Name

The system displays the name of the supplier. This name is based on the supplier ID selected.

Asset Reference Number


Specify the asset reference number. This field is enabled only if the 'With Asset' field is selected at the product level.

Asset Details

Insurance schedules are based on Asset value while contract booking, and subsequently change is based on written down value. You can capture the asset details by clicking 'Asset Values' button in 'Account Details' tab of the 'Account Details' screen.

5.1.2.1 Valuations Tab

You can capture valuation details of the asset in this tab.



The screenshot shows a window titled "Written Down Asset Values". Inside the window, there is a table with two columns: "Value Date" and "Asset Value". The table is currently empty. There are scroll bars on the right and bottom of the table area. The window has a standard Windows-style title bar with a diamond icon, a minus sign, and a close button.

Here, you can specify the following details related to your assets like vehicle, home, etc.

Assets

Select the type of asset from the drop-down list. The following values are provided for selection:

- Vehicle
- Home
- Others

Valuation Dt

Specify the valuation date for the selected asset, or select the date by clicking the 'Calendar' button.

Source

Specify the source associated with the asset selected.

Supplement

Specify the supplement of the valuation source used for the valuation.

Edition

Specify edition of the valuation source used for the valuation.

Wholesale

Specify the wholesale rate associated with the asset selected.

Retail

Specify the retail rate associated with the asset selected.

Usage

Specify usage level at the time of the valuation.

Usage Value +

Specify the initial usage value.

Total

Specify the total usage of the asset.

5.1.2.2 Vehicle Tab

You can capture details regarding the asset of type 'Vehicle' in this tab.

The screenshot shows a software window titled "Asset" with a tabbed interface. The "Vehicle" tab is active, displaying a form with the following fields and controls:

- Class:** A dropdown menu with a small icon to its right.
- Status:** A dropdown menu with a small icon to its right.
- Type:** A text input field.
- Sub Type:** A text input field.
- Asset Year:** A text input field.
- Asset Make:** A text input field.
- Asset Model:** A text input field.
- Asset Body:** A text input field.
- Reg#:** A text input field.
- Reg#:** A text input field.
- Address:** A text input field with a calendar icon to its right.

You can specify the following common details associated with asset of type vehicle:

Class

Select the class associated with the asset selected, from the option list. The following options are provided:

- New
- Used

Status

Select the status of the asset selected, from the option list. The following options are provided:

- Active
- Inactive
- Inventory
- Undefined

Type

Specify the type of the selected asset.

Sub Type

Specify the subtype associated with the asset, if any.

Year

Specify the year of association with the selected asset.

Make

Specify the make of the selected asset. For vehicle, you can specify the manufacturing company name and for home you can specify the name of the builder or developer.

Model

Specify the model of the selected asset.

Address

Specify the address associated with the asset.

You need to specify the following details additional related to vehicle type of asset:

Body

Specify the body number associated with the vehicle.

ID Number


Specify the unique identification number associated with the vehicle.

Reg. Number

Specify the registration number of the vehicle.

5.1.2.3 Home Tab

You can capture details regarding the asset of type Home in this tab.



You can specify the following additional details for home type of asset:

Occupancy

Specify the number of people occupying the house.

Width

Specify the width associated with the selected asset.

Length

Specify the length associated with the selected asset.

PO #

Specify the post office number of the location of the property.

GEO

Specify the property GEO code (Geospatial Entity Object Code) for the asset.

BNA

Specify the census tract/BNA code (Block Numbering Area) for the asset.

MSA

Specify the metropolitan statistical area (MSA) code for the asset.

Click 'OK' button to save the details.

Financial Details

You can capture the income or liability details of the customer in the 'Financials' screen. To invoke this screen, click on 'Financials' button in 'Account Details' tab of the Account Details screen.

5.1.2.4 Financials Tab

You can specify the following details related to the customer's income here:

The screenshot shows a window titled 'Financials' with a tabbed interface. The 'Financials' tab is active, and it contains a table with the following columns: Sequence Number, Type, Financial Source, Currency, Amount Financed, and Comment. The table is currently empty, and there are navigation icons (plus, minus, list) in the top right corner of the table area.

The following details are captured here:

Type

Select the type of the income from the option list provided.

Source

Specify the source of the income.

Currency

Select the currency associated with the income, from the option list provided.

Amount


Specify the amount associated with the income.

Comment

Specify any remarks or comments for the income.

5.1.2.5 Liability Tab

Here you can specify the following details related to the customer's liability:



The following details are captured here:

Type

Select the type of the liability from the option list provided.

Account Type

Specify the account type associated with the liability.

Currency

Select the currency associated with the liability, from the option list provided.

Amount

Specify the amount associated with the liability.

Frequency

Select the frequency at which payments are made towards the liability from the drop-down list. Following are the options available in the drop-down list:

- Daily
- Weekly
- Monthly
- Quarterly

- Half Yearly
- Yearly

Balance


Specify the current amount outstanding.

Comment

Specify any remarks or comments to be associated with the liability.

5.1.2.6 Other Income Tab

You can also capture the details related to other sources of income, if exists.



The following details are captured here:

Seq No

Specify the sequence number here.

Type

Specify the type of income here. You can also select the income type from the adjoining option list.

Currency

Specify the currency of the income here. You can also select the currency from the adjoining option list.

Amount

Specify the amount of income here.

Frequency

Select the frequency of the income here from the drop-down list. Following are the options available in the drop-down list:

- Daily
- Weekly
- Monthly
- Quarterly
- Half Yearly

- Yearly

Click 'OK' button to save the details.

5.1.3 Account Details Tab

You can capture the account details of the leasing account in this tab.

The screenshot shows the 'Account Details' window with the following sections:

- Account Information:** Branch, Account Number, Product, Product Category, Alternate Account Number, User Defined Status, User Reference, Authorisation Status.
- Financial Fields:** Value Date, Amount Financed, Maturity Extend By, Asset Reference, Maturity Date, Book Date, Down Payment, Original Start Date, Residual Amount, Subsidized Residual Amount, Residual Value, Currency, Net Principal.
- Applicant Information:** Primary Applicant (Customer Id, Customer Name), Other Applicants table.
- Effective Date and UDE Values:** Effective Date table and UDE Values table.

At the bottom, there is a navigation bar with links: MIS | GL Balance | IRR Details | Events | Installment | SWIFT Message Details | Asset Values | Securitization History | LBL_LIQORDER. The footer contains: Input By (Date Time), Authorized By (Date Time), Contract Status, and Authorized.

The following details regarding the leasing account are captured here:

Amount

The system displays the amount details.

Maturity Date

The system displays the date of maturity.

Value Date

The system displays the value date.

Book Date

The system displays the booking date.

Down Payment

The system displays the down payment details.

Currency

The system displays the currency details.

Asset Reference No

The system displays the asset reference number.

Subsidized Residual Amount

Specify the subsidized residual amount. However, this can be changed during VAMI.

Note

If the Subsidy Residual Amount check box is checked in the product level and if the subsidized residual amount is not specified, then the system displays an override message.

Primary Applicant

You can maintain the following details of the Primary applicants:

Customer ID

Specify the customer ID.

Customer Name

Specify the customer name.

Other Applicants

The details of the liability parties to the account are maintained in this field. You can specify the following details of the Co-applicants:

Customer ID

Select the customer ID from the option list.

Customer Name

The system displays the name of the customer.

Responsibility

Select the details of the co-applicants and their responsibility as a Co-signer or as a guarantor from the option list.

Liabilities%

Specify the liability of the co-applicant. You can also specify the percentage of interest split among different co-applicants.

Liability Amount

The system calculates and displays the upper limit of the liability in terms of the amount in this field. You may override the computed value.

Effective Date

Specify the effective date.

Holiday Periods

You can specify the following detail here:

Period

Select the period for which repayment holiday is to be given to the customer. The holiday periods maintained in the system are displayed in the adjoining option list

Effective Date

You can specify the following detail here:

Effective Date

The effective date is used to pick the UDE value. The system displays this date from the General UDE maintenance screen.

UDE Values

The system displays the UDE values from that of the UDE values maintenance screen. These values can be overridden by providing account level UDE values. However, the value can be maintained only for those UDEs defined at the product level. No New UDEs can be introduced at the account level.

You can specify the following details for the UDE values:

UDE ID

Specify the UDE ID from the option list.

UDE Values

Specify the Actual Value for the UDE based on the effective date in this field. The value specified here should fall within the minimum and maximum limits maintained for the UDE linked to the underlying product.

Rate Code

Select the code for the Floating Rates if any and the spread on it applicable in this field by clicking the option list.

Code Usage

Select the Code usage which can be periodic or automatic.

Resolved Value

This denotes the final value of a UDE. Resolved value = Rate code value taken from Floating Rate Maintenance + the spread [UDE Value]

5.1.4 Default Tab

The defaults are maintained by the bank. Depending upon the combination of various preferences, the bank can have various account preferences. The defaults primarily are based on product definition and can be overridden.

The screenshot shows the 'Account Details' window with the 'Default' tab selected. The form contains several sections:

- Header:** Includes 'New' and 'Enter Query' buttons, and navigation arrows.
- Fields:** Branch*, Account Number*, Product, Product Category, Alternate Account Number, User Defined Status, User Reference, and Authorisation Status.
- Navigation:** A menu bar with tabs: Main, Rollover/Renegotiation, Amendments, Account Details, Default (selected), Check List, Fields, Components, Charges, Linkages, Advice, Commitment, and Credit Score.
- Days: Liquidation:** Includes 'Liquidation mode' (set to 'Auto'), 'Auto Liquidate Reversed Payment', and 'Partial Liquidation' with 'Retries for Auto Liquidation' and 'Retries for Advice' input fields.
- Track Receivable:** Includes 'Auto Liquidation', 'Manual Liquidation', and 'Liquidate Back Valued Schedules' checkboxes.
- Loan Statement Notice:** Includes 'Liquidate Residual Value' checkbox, 'Loan Settlement Request' checkbox, 'Notice Date', and 'Expected Closure Date' fields.
- Reputation Basis:** Includes 'LBL_RATE_CHG_ACTION' and 'LBL_RECAMP_BASIS' dropdown menus, both set to 'LBL_CHG_INSTALLMENT'.
- Intermediary Details:** Includes 'Intermediary Initiated' checkbox and 'Intermediary Code' field.
- Project Financing:** Includes 'Project Account' checkbox.
- Footer:** A status bar with fields for 'Input By Date Time', 'Authorized By Date Time', 'Contract Status', and 'Authorized' checkbox. A navigation bar at the bottom lists: MIS | GL Balance | IRR Details | Events | Installment | SWIFT Message Details | Asset Values | Securitization History | LBL_LIQORDER.

Liquidation

You can maintain the following liquidation preferences:

Liquidation Mode

The system defaults the mode of liquidation from the product level. However you can modify the same to indicate the mode of liquidation that you are maintaining. You can select one of the following options:

- Manual
- Auto
- Component

Auto Liquidate Reversed Payment

If auto liquidation has been reversed in an account, it will be retried depending upon the status of this field. If this option is selected, then the auto liquidation is retried.

Partial Liquidation

If you select this option, system will perform partial auto liquidation.

Retries for Auto liquidation

When auto liquidation option is chosen and funds are not available, the number of times the system can retry auto liquidation is determined by this field.

If blank, the number of retries is infinite.

Retries Advice Days

Number of retries for an advice is defaulted here from the product maintenance level; however, you can modify if needed. The value should be less than the value maintained for 'Retries Auto Liquidation Days'.

Track Receivable

If Track receivable option is checked for an account, it tracks the amount to be liquidated as a receivable if funds are not available. So upon any subsequent credit, the receivables are blocked and allocated to the pending liquidation.

Auto Liquidation

Select this option to indicate that the Track receivable option is for Auto Liquidations.

Note

This is defaulted from the product level.

On schedule liquidation if there are insufficient funds in the settlement account to satisfy the liquidation and if both the product and the account are marked for receivable tracking then system initiates tracking of receivable.

If the account is marked for Partial liquidation, then liquidation happens to the extent of available funds, and the remaining amount is tracked.

If the account is not marked for partial liquidation, and the amount available in the settlement account is less than the due amount, then system won't do any liquidation and starts tracking the full due amount.

Whenever there is a credit to an account, the tracking process checks if the account has any receivable against it and if it does then the relevant amount is blocked as a receivable and the corresponding amount is marked to be used for settlement during subsequent ALIQ for the account. This process happens till the amount needed for liquidation is fully available.

The decision of allocating this credit will be based on the preference order of products that has been specified at an account class level. On the following EOD/BOD, batch liquidation tries to liquidate the schedule. The amount receivable is made available for the liquidation, and liquidation happens to the extent of receivable amount.

Manual Liquidation

Select this option to indicate that the Track receivable option is for Manual Liquidations.

Note

By default, the system selects this option.

Liquidate Back Value Schedules

On checking this field, the system liquidates the back value schedule in case of back value account.

Intermediary Details

You can capture the Intermediary Details at the account level to keep track of the accounts created through Intermediaries.

Intermediary Initiated

Check this box to indicate that the lease has been initiated by an intermediary.

Intermediary Code

If you have checked the box 'Intermediary Initiated', you need to specify the code of the intermediary who has initiated the lease. The adjoining option list displays all valid intermediary codes maintained in the system. You can select the appropriate one.

Note

Both the fields are disabled after the first authorization of the lease. They field cannot be modified during value-dated amendment and rollover operation.

Note that adjustment of commission and charge computed for the intermediary (in the past cycle) should be done manually in case of a reversal of any transaction done by the intermediary post the computation.

Loan Settlement Notice

The system displays the following loan settlement details based on the values specified at 'Value Dated Amendments' level:

- Loan Settlement Request
- Notice Date
- Expected Closure Date

5.1.5 Checklist Tab

The Check lists are maintained in the 'Check List Maintenance' screen and are linked to different events of the contract. The checklist maintained for the BOOK event is available in the Checklist tab at the time of account creation.

The screenshot displays the 'Account Details' window with the 'Check List' tab selected. The window includes a menu bar with 'New' and 'Enter Query' options, and a 'Go' button. The main area contains several input fields: 'Branch *', 'Account Number *', 'Product', 'Product Category', 'Alternate Account Number', 'User Defined Status', 'User Reference', and 'Authorisation Status'. A tabbed interface is visible with tabs for 'Main', 'Rollover/Renegotiation', 'Amendments', 'Account Details', 'Default', 'Check List', 'Fields', 'Components', 'Charges', 'Linkages', 'Advice', 'Commitment', and 'Credit Score'. The 'Check List' tab is active, showing a table with columns 'Description *' and 'Verified'. Below the table is a 'Remarks' section with a grid of 10 rows and 2 columns, each containing a text input field and a yellow speech bubble icon. At the bottom, there is a status bar with 'MIS | GL Balance | IRR Details | Events | Installment | SWIFT Message Details | Asset Values | Securitization History | LBL_UQORDER' and a footer with 'Input By Date Time', 'Authorized By Date Time', 'Contract Status', and a checkbox for 'Authorized'.

Check List

The following details are captured here:

Description

The system displays the description of the check list maintained for the BOOK event.

Verified

Check this box to indicate that the check list item has been verified

Remarks

Specify any additional remarks about the check list or the account in this free format text field

5.1.6 Fields Tab

The User Defined Fields are defined at the Product level. These fields are available in the Fields tab at the time of account creation.

The screenshot shows the 'Account Details' window with the 'Fields' tab selected. The window contains several input fields for account information:

- Branch *
- Account Number *
- Product
- Product Category
- Alternate Account Number
- User Defined Status
- User Reference
- Authorisation Status (dropdown)

Below the input fields is a navigation bar with tabs: Main, Rollover/Renegotiation, Amendments, Account Details, Default, Check List, Fields, Components, Charges, Linkages, Advice, Commitment, and Credit Score. The 'Fields' tab is active.

The 'Fields' section is divided into three categories:

- Number Fields:** A table with columns 'Field Name' and 'Field Value'.
- Character Fields:** A table with columns 'Field Name' and 'Field Value'.
- Date Fields:** A table with columns 'Field Name' and 'Field Value'.

At the bottom of the window, there is a status bar with the following text: MIS | GL Balance | IRR Details | Events | Installment | SWIFT Message Details | Asset Values | Securitization History | LBL_LIQORDER. Below this is a blue bar with the following text: Input By, Authorized By, Contract Status, and Authorized. Below the blue bar is a footer with the text: Date Time, Date Time.

The following details are displayed/ captured here:

UDF Description

The system displays all the UDF descriptions defined at the Product level.

UDF Value

Specify the UDF value in this field. This is applicable only if the user input or list of values is defined at the time of creation of the UDF.

5.1.7 Components Tab

Clicking against the 'Components' tab in the 'Account Details' screen invokes the following screen:

The screenshot displays the 'Account Details' window with the 'Components' tab selected. The interface includes a top navigation bar with tabs like 'Main', 'Rollover/Renegotiation', 'Amendments', 'Account Details', 'Default', 'Check List', 'Fields', 'Components', 'Charges', 'Linkages', 'Advice', 'Commitment', and 'Credit Score'. The 'Components' tab is active, showing a 'Schedule' table with columns: Type, Schedule Flag, Formula, First Due Date, Number, Frequency, Unit, Due Date On, End Date, Amount, and EMI Am. Below the schedule table is a 'Details' table with columns: Schedule Number, Due Date, Amount Settled, Amount Due, EMI Amount, Amortize Principal, Accrued Amount, and Waive. The 'Details' table is currently empty.

You can specify the following details for the components:

Description

After you specify the component Name, the system displays the description of the component.

Component Currency

The system displays the currency associated with the component. The value is defined at Product level.

Special Interest Amount

Specify the amount for the special interest.

Settlement Ccy

Select the settlement currency for the option list. The settlement currency is maintained as a default for both Credits and Debits.

Dr. Payment Mode

Select the debit payment mode from the drop-down list. Following are the options available in the drop-down list:

- CASA
- Credit Card
- Debit Card
- Clearing
- External Account
- Electronic Pay Order
- Internal Check
- Instrument
- GIRO
- Cash/Teller

Liquidation Mode

The system defaults the mode of liquidation from the product level. However you can modify the same to indicate the mode of liquidation of the component from the drop-down list. The following options are available for selection:

- Auto
- Manual

Note

This is applicable only if 'Liquidation mode' is selected as 'Component' at the account preference level.

Main component

The system selects the component of the lease designated as main component in the product level in this field.

Verify Fund

Select this option to indicate whether the system should verify the availability of sufficient funds in the customer account before doing auto liquidation of the component.

Capitalized

Select this option if the scheduled amounts are to be capitalized.

Waive

Select this option to waive the component for the account.

Penal basis Comp options

The system displays the penal basis for calculating penalty component.

Service Branch

Specify the branch that services the customer account.

Service Account

Specify the account in the service branch.

Note

All modes except CASA needs service account. Adjustments etc. are settled through this account.

Component Type

Specify the nature of the component. This is also known as the 'Reporting Type'. It defines the manner in which the component should be classified for reporting/ accounting purposes. A component can be of one of the following types:

- Reimbursement: these are components which have both Dr and Cr mapped to settlement accounts
- Off-Balance Sheet (OBS): An OBS Component will have balances but these need not be zero when an account is closed
- Adhoc Charges
- Charge
- Tax
- Insurance
- Interest
- Provisioning
- Deposit

Cr. Payment Mode

Select the credit payment mode from the drop-down list. Following are the options available in the drop-down list:

- CASA
- Clearing
- External Account
- Instrument
- Cash/Teller

Special Interest

Select this option to denote if the component is a special interest type. This implies that the computed value of the component can be overridden with the entered value.

IRR Applicable

Check this option to indicate that the component is to be considered for IRR calculation for the account.

This field will not be available for input if 'Accrual Required' and 'IRR Applicable' are left unchecked at the product level.

Schedule

The schedules can be for two types, namely,

- Schedules for financial lease
- Schedules for operational lease

5.1.7.1 Schedules for Financial Lease

For Advance payment type and for complete disbursement during initiation, the payment schedules for principal and interest are populated with start date as value date, due date as schedule start date. The first EMI schedule will be liquidated during the initiation. Accounting entries are passed with DSBR event.

For Arrears payment type and for complete disbursement during initiation, the payment schedules for principal and interest are populated with start date as value date and due date as schedule end date. Schedules will be liquidated on due date.

For multiple disbursements (Lease advances), the EMI schedules will not be populated in this case. Pre- EMI interest is collected by defining interest schedules. This is applicable for both modes of payment.

Note

EMI schedules are populated once the total amount is disbursed (On SCHR event)

If a residual amount exists for the lease account, then the system will consider the residual amount as the last schedule of the contract with the due date as the maximum date supported (global maximum date) with the components as PRINCIPAL and INTEREST. The residual amount in case of payment in advance includes the interest.

Payment schedules are populated based on the frequency and frequency units maintained at product level; however this can be changed at account level.

5.1.7.2 Schedules for Operational Lease

For an operational lease, disbursement schedules are restricted. On value date of the lease account, along with INIT, DSBR will fire for down payment and first EMI will be liquidated if the payment mode is Advance. If the payment mode is Arrears, the schedule due date will be the schedule end date.

If a residual amount exists for the lease contract, then that would be the last schedule of the contract with the due date as the maximum date supported (global maximum date) and the component INTEREST. The residual amount in case of payment in advance includes the interest.

Note

The frequency and frequency units of multiple schedules should be the same.

Click 'Edit' button to make any change to the scheduling. The following details are captured here:

Type

Select the type of schedule from the option list. Schedule can be a payment, a disbursement or a rate revision schedule.

Schedule Flag

Select the Schedule flag from the option list.

Formula

Specify the formula used to compute the component for that schedule.

