

Common Core - Core Entities and Services User Guide

**Oracle FLEXCUBE Universal Banking**

Release 14.5.3.0.0

**Part No. F50379-01**

November 2021

Common Core - Core Entities and Services User Guide  
Oracle Financial Services Software Limited  
Oracle Park

Off Western Express Highway  
Goregaon (East)  
Mumbai, Maharashtra 400 063  
India

Worldwide Inquiries:

Phone: +91 22 6718 3000

Fax: +91 22 6718 3001

<https://www.oracle.com/industries/financial-services/index.html>

Copyright © 2007, 2021, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are “commercial computer software” pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

---

# Contents

<b>1. Preface</b>	<b>1-1</b>
1.1 Introduction	1-1
1.2 Audience	1-1
1.3 Documentation Accessibility	1-1
1.4 Organization	1-1
1.5 Glossary of Icons	1-2
1.6 Related Documents	1-2
<b>2. Core Maintenances</b>	<b>2-1</b>
2.1 Introduction	2-1
2.2 Bank and Branch Core Parameters Maintenance	2-1
2.2.1 Invoking Bank Core Parameters Maintenance Screen	2-2
2.2.2 Invoking Branch Core Parameter Maintenance Screen	2-3
2.3 Maintaining Host Code	2-4
2.3.1 Invoking Host Code Maintenance Screen	2-5
2.3.2 Viewing Host Code Maintenance Summary	2-6
2.4 Local Holiday Maintenance	2-6
2.4.1 Maintaining Local Holiday Calendar	2-7
2.4.2 Annual Holidays	2-8
2.5 Country Code Maintenance	2-8
2.5.1 Maintaining Country Name Details	2-9
2.6 Currency Maintenance	2-10
2.6.1 Maintaining Currency Definition	2-10
2.6.2 Maintaining Currency Position GL	2-23
2.6.3 Viewing Currency Summary Details	2-24
2.6.4 Maintaining Currency Pair	2-25
2.6.5 Viewing Currency Pair Summary	2-28
2.6.6 Maintaining Currency Rate Type	2-29
2.6.7 Maintaining Currency Exchange Rates	2-29
2.6.8 Viewing Exchange Rates	2-32
2.7 Currency Holiday Maintenance	2-33
2.7.1 Maintaining Currency Holiday Calendar	2-33
2.7.2 Steps to Define Currency Holidays	2-34
2.7.3 Defining Currency Holidays	2-35
2.8 Floating Rates Definition	2-35
2.8.1 Invoking LD MM Floating Rate Input Screen	2-35
2.8.2 Invoking Rate Code Definition Screen	2-36
2.8.3 Capturing Currency Details	2-38
2.8.4 Specifying Effective Date and Amount Slab Details	2-38
2.8.5 Tenor and Interest Rate Details	2-39
2.8.6 Rate Code Usage	2-39
2.9 External Entities Maintenance	2-41
2.9.1 Maintaining External Chart of Accounts	2-41
2.9.2 Maintaining External Transaction Code	2-42
2.9.3 Maintaining External Credit Approval	2-43
2.9.4 Maintaining External Customer Input	2-43
2.9.5 Viewing External Customer Summary	2-45

2.9.6	<i>Maintaining External Customer Account</i>	2-46
2.9.7	<i>Mapping External Multi Currency Accounts</i>	2-48
2.9.8	<i>Maintaining External Consumer Loan Account</i>	2-49
2.10	External Limit Entities Maintenances	2-50
2.10.1	<i>Maintaining External Collaterals</i>	2-50
2.10.2	<i>Maintaining External Collateral Pools</i>	2-53
2.10.3	<i>Maintaining External Facilities</i>	2-54
2.10.4	<i>Maintaining External Liability Linkage</i>	2-57
2.10.5	<i>Maintaining External Liability</i>	2-58
2.11	Settlement Details Maintenance	2-59
2.11.1	<i>Capturing the BIC Code Details</i>	2-59
2.11.2	<i>Viewing BIC Codes</i>	2-62
2.11.3	<i>Associating Customer to a BIC Code</i>	2-63
2.11.4	<i>Viewing Customer BIC Codes</i>	2-64
2.11.5	<i>Operations on a BIC Record</i>	2-65
2.11.6	<i>Maintaining Local Payments Bank Directory</i>	2-66
2.11.7	<i>Viewing Local Payments Bank Directory Details</i>	2-70
2.11.8	<i>Maintaining Bank Directory Plus</i>	2-71
2.11.9	<i>Viewing Bank Directory Plus Details</i>	2-72
2.11.10	<i>Maintaining IBAN Plus</i>	2-74
2.11.11	<i>Viewing IBAN Plus Details</i>	2-75
2.11.12	<i>Maintaining BICPlusIBAN</i>	2-76
2.11.13	<i>Viewing BICPlusIBAN</i>	2-77
2.11.14	<i>Maintaining IBAN Information</i>	2-77
2.11.15	<i>Viewing IBAN Information</i>	2-79
2.11.16	<i>Uploading BIC Files</i>	2-80
2.11.17	<i>IS File Upload</i>	2-80
2.11.18	<i>BIC Record File Formats</i>	2-81
2.11.19	<i>Local Bank Directory View</i>	2-84
2.12	MIS Details Maintenance	2-86
2.12.1	<i>Maintaining MIS Class</i>	2-86
2.12.2	<i>Saving the Record</i>	2-88
2.12.3	<i>Maintaining MIS Group</i>	2-89
2.12.4	<i>Operations on the MIS Group Record</i>	2-89
2.12.5	<i>Maintaining MIS Cost Codes</i>	2-90
2.12.6	<i>Operations on the MIS Cost Code Record</i>	2-92
2.12.7	<i>Maintaining MIS Pool</i>	2-92
2.13	User Defined Fields Maintenance	2-93
2.13.1	<i>Invoking the User Defined Fields Maintenance Screen</i>	2-93
2.13.2	<i>Mapping UDF Function Field</i>	2-94
2.14	Generic Interface Maintenance	2-94
2.14.1	<i>Invoking GI Process</i>	2-97
2.14.2	<i>Viewing Error Details of Individual Record</i>	2-98
2.14.3	<i>Specifying Interface Definition Details</i>	2-99
2.14.4	<i>Viewing Interface Definition Summary</i>	2-107
2.14.5	<i>Maintaining AUDF (ASCII User Defined Function) Details</i>	2-109
2.14.6	<i>Viewing AUDF Summary Details</i>	2-110
2.14.7	<i>Maintaining Translation Details</i>	2-111
2.14.8	<i>Viewing Translation Summary Details</i>	2-112
2.14.9	<i>Maintaining CRC Algorithm Details</i>	2-113



2.14.10	Viewing CRC Summary Details.....	2-114
2.15	Process Definition.....	2-115
2.15.1	Maintaining Process Codes.....	2-115
2.16	Reporting Parameters Maintenance.....	2-116
2.16.1	Maintaining Report Spool Path.....	2-116
2.17	Maintaining Amount Text.....	2-117
2.18	Dynamic Package - DML Execution.....	2-118
2.19	Maintaining Alternate Risk Free Rates.....	2-119
2.20	Customer Account Entitlement Group Maintenance.....	2-121
<b>3.</b>	<b>Function ID Glossary .....</b>	<b>3-1</b>

---

# 1. Preface

## 1.1 Introduction

This manual is designed to help you quickly get acquainted with the Common Core - Core Entities and Services module of Oracle FLEXCUBE.

You can further obtain information specific to a particular field by placing the cursor on the relevant field and striking <F1> on the keyboard.

## 1.2 Audience

This manual is intended for the following User/User Roles:

Role	Function
Back office clerk	Input functions for contracts
Back office managers/officers	Authorization functions
Product Managers	Product definition and authorization
End of day operators	Processing during end of day/ beginning of day
Financial Controller/Product Managers	Generation of reports

## 1.3 Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.





## 1.4 Organization

This manual is organized as follows:

Chapter	Description
Chapter 1	<i>Preface</i> gives information on the intended audience. It also lists the various chapters covered in this User Manual.
Chapter 2	Core Maintenances explains the maintenance of various basic details about your bank.
Chapter 3	<i>Function ID Glossary</i> has alphabetical listing of Function/Screen ID's used in the module with page references for quick navigation.

## 1.5 Glossary of Icons

This User Manual may refer to all or some of the following icons.

Icons	Function
	Exit
	Add row
	Delete row
	Option List

## 1.6 Related Documents

For further information on procedures discussed in the manual, refer to the Oracle FLEXCUBE manuals on:

- Common Procedures
- Accessibility
- Messaging
- Core Services
- Core Entity
- Generic Interface

---

## 2. Core Maintenances

### 2.1 Introduction

This chapter contains the following sections:

- [Section 2.2, "Bank and Branch Core Parameters Maintenance"](#)
- [Section 2.3, "Maintaining Host Code"](#)
- [Section 2.4, "Local Holiday Maintenance"](#)
- [Section 2.5, "Country Code Maintenance"](#)
- [Section 2.6, "Currency Maintenance"](#)
- [Section 2.7, "Currency Holiday Maintenance"](#)
- [Section 2.8, "Floating Rates Definition"](#)
- [Section 2.9, "External Entities Maintenance"](#)
- [Section 2.10, "External Limit Entities Maintenances"](#)
- [Section 2.11, "Settlement Details Maintenance"](#)
- [Section 2.12, "MIS Details Maintenance"](#)
- [Section 2.13, "User Defined Fields Maintenance"](#)
- [Section 2.14, "Generic Interface Maintenance"](#)
- [Section 2.15, "Process Definition"](#)
- [Section 2.16, "Reporting Parameters Maintenance"](#)
- [Section 2.17, "Maintaining Amount Text"](#)
- [Section 2.18, "Dynamic Package - DML Execution"](#)
- [Section 2.19, "Maintaining Alternate Risk Free Rates"](#)
- [Section 2.20, "Customer Account Entitlement Group Maintenance"](#)

### 2.2 Bank and Branch Core Parameters Maintenance

This section contains the following topics:

- [Section 2.2.1, "Invoking Bank Core Parameters Maintenance Screen"](#)
- [Section 2.2.2, "Invoking Branch Core Parameter Maintenance Screen"](#)

## 2.2.1 Invoking Bank Core Parameters Maintenance Screen

You can invoke 'Bank Core Parameters Maintenance' screen by typing 'STDCRBNK' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Bank Core Parameters Maintenance

Enter Query

Bank Code \*  Bank Name

Head Office Branch

Branch Code \*  Branch Description

No of Days to Forget Customer

Maker Date Time: Mod No Record Status  
Checker Date Time: Authorization Status

You can specify the following fields:

### **Bank Code**

Specify the bank code.

### **Bank Name**

The name of the bank is displayed here.

### **Head Office Branch**

#### **Branch Code**

Specify the head office branch code.

#### **Branch Description**

The description of the branch is displayed here.


#### **No. of days to Forget Customer**

Enter the number of days, after which the system will forget the customer after they close their account. Once the customer is forgotten you can't view the details of the customer.

Click "Execute Query". The records matching the entered query criteria is displayed.

## 2.2.2 Invoking Branch Core Parameter Maintenance Screen

You can invoke 'Branch Core Parameter Maintenance' screen by typing 'STDCRBRN' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



You can specify the following fields:

### Host Code

Specify the host code here. Alternatively, you can also select the host code from the adjoining option list.

### Branch Code

Specify the branch code here.

### Country Code

Specify the country code here.

### Branch Name

Specify the branch name here.

### Branch Address

Specify the address of branch here.

### Local Currency

Specify the local currency of the branch. Alternatively, you can also select the currency from the adjoining option list.

### Walk in Customer

Specify the walking customer name here. Alternatively, you can also select the walk in customer name from the adjoining option list.

### Weekly Holiday 1 & 2

Select the weekly holiday of the branch from the drop-down list. The list displays the following values:

- Sunday
- Monday
- Tuesday
- Wednesday
- Thursday

- Friday
- Saturday

### **Auto Authorization**

Check this box to indicate that the branch allows auto authorization facility.

### **Host Name**


Specifies the host name from which the customer is logged in.

### **Report DSN**

Specify the Report DSN details.

### **Maintaining SWIFT Address Details**

You can maintain SWIFT address details for the branch in the 'SWIFT Address' screen. Click "Swift Address" button to invoke the screen.



### **SWIFT Address**

Specify the required SWIFT Address. Alternatively, you can also select the SWIFT address from the adjoining option list.

### **Default BIC**

Check this box to use the default BIC.

## **2.3 Maintaining Host Code**

You can group branches in the same zone or region under a Host for specific processing. You can have multiple hosts depending on processing requirements. These hosts can be maintained in Host Code Maintenance screen.

This section contains the following topics:

- [Section 2.3.1, "Invoking Host Code Maintenance Screen"](#)
- [Section 2.3.2, "Viewing Host Code Maintenance Summary"](#)

## 2.3.1 Invoking Host Code Maintenance Screen

You can invoke 'Host Code Maintenance' screen by typing 'STDHSTCD' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a 'Host Code' maintenance window. The title bar reads 'Host Code' and the subtitle is 'New'. The main area contains five input fields with red asterisks indicating they are required: 'Host Code \*', 'Description \*', 'Country Code \*', 'Processing Time Zone \*', and 'Default Branch Code'. The bottom section is a status bar with the following fields: 'Maker', 'Checker', 'Date Time:', 'Date Time:', 'Mod No', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

You can specify the following fields:

### Host Code

Specify the processing zone that is applicable for the requests.

### Host Description

Specify the description of the host code.

### Country

Specify the required country code from the list.

### Processing Time Zone

Specify the time zone that is used for processing the request. All open and authorized time zones are available in the list.

### Default Branch

Specify the required branch code which indicates the main branch of the group of branches linked to the same host code. All valid branches are available in the list.



## 2.3.2 Viewing Host Code Maintenance Summary

You can invoke 'Host Code Maintenance Summary' screen by typing 'STSHSTCD' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a web application window titled "Host Code Maintenance Summary". At the top, there are search options: "Search", "Advanced Search", and "Reset". Below this is a search criteria section with the following fields:

- Authorization Status:  (dropdown arrow)
- Record Status:  (dropdown arrow)
- Host Code:  (magnifying glass icon)
- Country Code:  (magnifying glass icon)
- Processing Time Zone:  (magnifying glass icon)
- Default Branch Code:  (magnifying glass icon)

Below the search fields, there is a pagination bar showing "Records per page 15", "1 Of 1", and a "Go" button with a dropdown arrow.

The main area is a table with the following columns: Authorization Status, Record Status, Host Code, Description, Country Code, Processing Time Zone, and Default Branch Code. The table contains 15 rows, each with a checkbox in the first column. The table is currently empty.

An "Exit" button is located in the bottom right corner of the window.

You can search using one or more of the following parameters:

- Authorization Status
- Record Status
- Host Code
- Country Code
- Processing Time Zone
- Default Branch Code

Once you have specified the search parameters, click 'Search' button. The system displays the records that match the search criteria for the following:

- Authorization Status
- Record Status
- Host Code
- Description
- Country Code
- Processing Time Zone
- Default Branch Code

## 2.4 Local Holiday Maintenance

For a year, you need to define your weekly holidays and your calendar year annual holidays. This is done in the 'Local Holiday Calendar' screen.

The system uses the information maintained in this screen to do the following:

- To check that the 'value date' of no Data Entry transaction falls on a holiday

- To check that the start date / maturing date and schedule date of a loans and deposit contract does not fall on a holiday
- To effect a date change on the system -- today's date and the next working date

For any schedule / contract maturing at a future date, say, 5 years hence, you can input a future date, only if the calendar for that year has been maintained. It is not necessary to maintain the list of all annual holidays, for future, you can merely define all regular weekly holidays.

This screen is maintained for each branch, of your bank, from the respective branches; thus making it possible to have a different set of holidays for different branches of the bank.

This section contains the following topics:

- [Section 2.4.1, "Maintaining Local Holiday Calendar"](#)
- [Section 2.4.2, "Annual Holidays"](#)

## **2.4.1 Maintaining Local Holiday Calendar**

Invoke the 'Local Holiday Calendar' screen, by typing 'STDLOCHL' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

---

### **Note**

It is possible to maintain next working day as a holiday and next holiday as a working day.

---

In this screen you can specify the weekly and also the annual holidays, for your branch, for any year between 1 AD and 4000 AD.

### **Steps to Define Yearly Holidays**

To define holidays for a year, (for instance, for 2000) you have to do the following:

Building the calendar for the year

#### **Step 1**

Select 'New' from the Actions menu in the Application tool bar or click new icon


#### **Step 2**

Enter the year -- 2000 or move to the year 2000 using the arrows

#### **Step 3**

To build the calendar for the year, 2000 click the 'Refresh' button. This button is called the 'refresh / build up' button because it builds the calendar for you. Please note:

- On invoking the calendar of any year, you will notice that Saturdays and Sundays are marked as weekly holidays. This is the default setting of the system
- For identification, the working days are marked in black and the holidays in red.



## Defining Holidays

To define annual holidays, click on the particular date to mark the selected date as a holiday.

If you want to unmark a day specified earlier as a holiday, double click on it, once again. You will notice that the day gets marked in black.

### 2.4.2 Annual Holidays

These are the holidays you have defined for the year calendar on display

You will observe that all holidays are marked in red, while working days in black. (All unauthorised holiday dates appear against a blue background). To mark a date as a holiday, double click on it. In case you wish to undo a date marked off as a holiday, double click on it once again. It changes back to a working day.

With each modification you make, the Modification Number in the made by column below moves up serially.

## 2.5 Country Code Maintenance

This section contains the following topics:

- [Section 2.5.1, "Maintaining Country Name Details"](#)

## 2.5.1 Maintaining Country Name Details

You can define country name through the 'Country Code Maintenance' screen. You can invoke this screen by typing "STDCNMNT" in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Country Code Maintenance' application window. The window title is 'Country Code Maintenance'. It features a menu bar with 'New' and 'Enter Query'. The main area contains several input fields: 'Country Code \*', 'Country Name', 'Alternate Country Code', 'ISO Country Code', 'Default Clearing Network', and 'International Dialing Code +'. There are also three checkboxes: 'Blacklisted', 'EU Member', and 'Generate 205'. On the right side, there are two more checkboxes: 'IBAN Mandatory for Payment Messages' and 'Clearing Code in BIC+'. At the bottom, there is a 'Fields' section with columns for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

Here, you can capture the following details

### Country Code

You can capture a unique three-character code to identify the country. For example: you can maintain USA as the country code for United States of America.

### Alternate Country Code

You can also associate an alternate country code. This is for information purposes only and will not be printed on any customer correspondence.

For example you can have US as the alternate code for USA

### Country Name

After you define an alphanumeric code to identify the country for which you would like to assign a name, you have to specify the name of the Country.

### Blacklisted

Further, in the 'Country Name Maintenance' screen you can black list a country for further usage. You are not allowed to deal in countries that are blacklisted.

You can only deal with countries that are *not* blacklisted

### IBAN Mandatory for Payment Messages

If this is checked, it indicates that for every payment message an IBAN is mandatory.

If this option is unchecked for a country, the system will not process the outgoing payments wherein the ordering customer or the beneficiary customer belongs to that country.

### EU Member

This indicates whether the country is recognized by Swift as a part of the Intra European countries.

If you check this flag the instructed amount field should be mandatory in the generated 103, 103+ and 102 messages. The instructed amount field is mandatory in the incoming messages.

#### **Clearing Code in BIC+**

Check this box to indicate that the National ID in the BIC plus file is the clearing code. During upload of clearing codes from BIC plus file, the records that belong to countries against which this box is checked will be selected.

#### **Generate 205**

Check this box to indicate that the cover message 205COV or 205 need to be generated for transactions involving this country. If you do not select this option, RTGS, 202 or 202COV message will be generated.

*For more details on 202COV and 205COV cover message formats, refer settlements user manual.*

#### **Default Clearing Network**

Once the National ID from BIC plus directory is uploaded into clearing codes, the network will be populated as the default clearing network for that country. This is mandatory when clearing code in BIC+ is chosen as 'Y'.

#### **International Dialling Code**

Specify the international dialling code associated with the country.

## **2.6 Currency Maintenance**

This section contains the following topics:

- [Section 2.6.1, "Maintaining Currency Definition"](#)
- [Section 2.6.2, "Maintaining Currency Position GL"](#)
- [Section 2.6.3, "Viewing Currency Summary Details"](#)
- [Section 2.6.4, "Maintaining Currency Pair"](#)
- [Section 2.6.5, "Viewing Currency Pair Summary"](#)
- [Section 2.6.6, "Maintaining Currency Rate Type"](#)
- [Section 2.6.7, "Maintaining Currency Exchange Rates"](#)
- [Section 2.6.8, "Viewing Exchange Rates"](#)

### **2.6.1 Maintaining Currency Definition**

In the 'Currency Definition' screen, you define the attributes of the currencies in which your bank can deal. For each currency, you can define attributes like, the SWIFT code for the currency, the country to which the currency belongs, the interest method, the spot days, the settlement days, etc.

Currencies can be maintained only at the Head Office. The list of currencies will be made available to the branches based on the currencies that have been defined for the country linked to that branch.

Invoke this screen by typing 'CYDCDEFE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Currency Definition' application window. The window title is 'Currency Definition' and it has a 'New' button and an 'Enter Query' field. The form contains several input fields: 'Maintenance Country \*', 'Currency Code \*', 'Currency Name', 'Currency Type', 'ISO Numeric Currency Code', 'Currency Country', 'Decimals', 'Interest Method' (a dropdown menu showing '30-Euro/360'), 'Spot days', 'Foreign Exchange Netting Days', 'Settlement Message Days', 'Cutoff Time', 'Maintenance Country Name', 'Alternate Currency Code', 'Tolerance Limit', 'Index Base Currency', and 'Commodity Code'. At the bottom, there is a navigation bar with 'PC | Currency Country Mapping | Fields' and a table with columns for 'Maker', 'Date Time', 'Mod No', 'Record Status', 'Checker', 'Date Time', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

## **Maintaining Currency Details**

### **Maintenance Country**

Specify the country code for which the currency is maintained. Alternatively, you can select the country code from the option list. The list displays all the authorized and open country codes along with their description maintained in the system.

For example, if you maintain the country code for a bank or a branch, which is operating in Singapore for the currency USD, then you should specify the country code as SG. The system defaults the field 'Country' as US.

### **Maintenance Country Name**

The system displays the name of the country for which the currency is maintained.

### **Currency Code**

Currencies are identified in Oracle FLEXCUBE by the SWIFT codes assigned to them. The currency will be identified by this code in all transactions that involve it.

### **Currency Name**

You can enter the detailed name of the currency in not more than thirty-five alphanumeric characters.

### **Currency Type**

As per your bank's requirement you can choose to classify currencies into different currency types. The bank can use its own discretion to decide the basis of classifying currencies into different currency types. A currency type can consist of a maximum of three characters.

Depending on the customer account mask maintained, the value in the currency type field would be used during the generation of customer account numbers through the Customer Accounts Maintenance screen.

If you have decided to include currency type as part of the customer account number (in the account number mask), then at the time of creating a new customer account number, you will

need to select the currency of the account number being generated. In the option-list provided for currency, the currency code is displayed along with the associated currency type say, USD – 1, GBP – 2 etc. When the account number gets populated, it is the currency type that forms a part of the customer account number.

### **ISO Numeric Currency Code**

Specify the currency code specified by the International Standardization Organization.

### **Country**

After you have identified the currency, you should indicate the country to which the currency belongs. You can select a country code from the option list available.

### **Decimals**

You can indicate the number of decimal units up to which the currency can be denominated. The number of decimals allowed for any amount in the currency can be:

0 - Currency with no decimals

2 - Currency with two decimals

3 - Currency with three decimals

4- Currency with four decimals

### **Interest Method**

You can indicate the interest rate to be used for transactions that involve this currency. The interest options available are:

- Actual/Actual
- 30(US)/360
- Actual/360
- 30(Euro)/365
- 30(US)/365
- Actual/365
- 30(Euro)/Actual
- 30(US)/Actual
- Actual/Actual

Select the interest method that should be used by default whenever the currency is used in transactions. While processing a transaction that involves this currency, the interest method defined for the currency is defaulted. You have the option to change it for a specific transaction.

However, if you do not specify an interest method for a transaction, the method defined for the currency will be used (For details refer to Annexure on Page 140).

### **Spot Days**

The number of spot working days applicable for the currency is specified here.

For example, the tenor of an MM contract is as follows:

**Value Date** - 01/01/99

**Maturity Date** - 31/01/99

**Contract Currency** - USD

## **Contract Amount - 5000**

For USD, the number of Spot Days is specified as: **Spot Days - 3**

For this contract, the payment advices will be sent on 28/01/96.

## **Foreign Exchange Netting Days**

Oracle FLEXCUBE provides a facility wherein all transactions relating to a customer, meant to be settled on a particular day and are made before a specific cut off day are collated, netted and a single payment message is sent instead of individual messages for each payment. This cut off day can be parameterized and is called 'Netting Days'. The number of FX netting days applicable for the specified currency is maintained here.

---

### **Note**

The system will validate that the FX Netting days are lesser than or equal to the spot days.

---

## **Settlement Days**

In this screen, you can specify the 'Settlement Days' for a currency. Settlement messages for the components of a contract (in the LC, BC, LD, MM and FX modules) will be generated according to the settlement days specified for the currency of the settlement account. The following example illustrates this.

For example, when maintaining the details of USD in the Currency screen, you specify the 'Settlement Days' as '2'. This implies that two working days prior to the settlement of a component through a USD account, a settlement message will be automatically generated if specified (when you run the Settlement Messages function at the end of day).

The settlement details of a contract are as follows:

Settlement Date: 06 May 1999

Settlement Account Currency: USD

Component: Principal

Settlement Message: **Yes**

Component Currency: GBP

When you generate the Settlement Messages function, at the end of day, on 04 May 1999, a settlement message for the Principal component of the contract will be generated.

You can run Settlement Messages function as part of EOD operations from the Application Browser to automatically generate settlement messages for contracts marked out for automatic liquidation.

The settlement day specification for a currency will determine the contracts that are picked up for settlement message generation.

## **Cut-off Time**

The Currency Cut-off time refers to the time by which all transactions involving a currency should be generated. For a currency, you can indicate the cut-off hour and minute. This time should be expressed in the local time of the bank.

The maintenance of a cut-off time for a currency has particular reference to outgoing funds transfers involving it.



## Cut-off days

You can also specify the cut-off days and time for payment transactions involving the currency.

For example, the value date of a funds transfer transaction (incoming payment) involving USD, is 3<sup>rd</sup> June 2001. The number of cut-off days specified for the currency is 2. This means that the payment must be received on or before 1<sup>st</sup> June 2001. If the payment is received on 1<sup>st</sup> June, it must be received before the cut-off time specified for USD.

If the USD cut-off time is 1200 hrs, then, if the payment is received on 1<sup>st</sup> June 2001, it must be received before 1200 hrs.

The cut-off time (in hours and minutes) that you maintain to be applicable for payment transactions involving a currency are applicable to the head office branch of your bank.

If the branches are in time zones other than the head office branch time zone, you must maintain the offset time applicable for each branch, in the Branch Parameters screen.

---

### Note

Even when cut-off days and cut-off time for a currency have both been specified, the cut-off checks are performed for a funds transfer transaction only if specified as applicable for the product involved in the transaction.

---

## Tolerance Limit

When you are maintaining an 'In' Currency, or the Euro, in the Currency Definition screen, you can define a 'Tolerance Limit' for it. The limit is expressed as a percentage.

### The implication:

During the transition period, settlement of components in 'In' currencies can be made either in the same currency or in the Euro (EUR) depending on the settlement account(s) maintained. (Similarly, components in Euro can either be settled in EUR or in an 'In' currency.) In the settlement messages that are generated (MT 100, MT202), the settlement amount would be reported in the Settlement Account Currency. However, you can opt to additionally furnish the value of the component in Euro Related Information (ERI) currency. You have to manually specify the settlement amount value, in the ERI currency, in the Settlement Message Details screen.

When generating the message towards settlement (MT100, MT202), the system ensures that the value you specify as the ERI Amount conforms to the Tolerance Limit defined for the ERI Currency (in the Currency Definition screen). That is, the system computes the ERI equivalent of the settling amount using the pegged rates, and compares the same against the ERI amount input by the user. If the difference is within the tolerance limits defined for the ERI currency, the user specified amount is used.

If the user specified ERI amount breaches the Tolerance Limit defined for the ERI currency, the system calculates and reports the ERI Amount on the basis of the exchange rate defined for the settlement currency vis-à-vis the ERI currency.

For example, in the SWIFT messages (MT 100 and MT 202) that are generated towards settlement, the value of the component can be reported both in Nostro account currency (in Field 32A) and in an ERI currency that you specify (in Field 72). In Oracle FLEXCUBE, this information is captured in the European Related Information (ERI) fields in the Settlement Message Details screen.

Assume the following scenario:

- The settlement account is an EUR account
- You have to settle an amount of DEM 10000
- You have defined the ERI currency for DEM as DEM
- The Tolerance Limit for DEM as 0.05%
- The exchange rate: 1 Euro = 1.30 DEM

The settlement amount in Euro would therefore be 7692.36 (rounded to nearest higher cent). This amount will be reported in Field 32A of the settlement messages. Now, if you want to furnish the settlement amount in the ERI currency (in this case, DEM) you have to manually enter the DEM value in the ERI Amount field. You may enter DEM 10000. (EUR 7692.36 actually converts into DEM 10000.068.)

The value that you have entered is well within the Tolerance Limit of 0.05% defined for DEM. Therefore, this value will be reported in Field 72 of the settlement messages.

Since the Tolerance Limit for DEM is 0.05%, you can specify an ERI Amount between DEM 9995 and DEM 10005 ( $DEM\ 10000 * 0.05/100 = DEM\ 5$ ). If you enter an ERI value exceeding DEM 10005 or less than DEM 9950, the system recalculates the ERI Amount at the time of generating the settlement messages. The recalculation will be on the basis of the pegged rates between the Settlement Currency and the ERI currency.

---

#### Note

The system validates the ERI amount only when generating the settlement messages. It does not validate the ERI amount at the time of input (in the Settlement Message Details screen).

---

#### Index Base Ccy

Specify the currency that should be used to handle index-based securities traded by the banks, wherein the deals are done in index currency and their settlement is done through the local currency.

#### Commodity Code

Check this box to indicate that maintained currency code is a commodity code which is restricted not to populate in payment messages during message generation in the currency code field.

#### Generate 103+

You can enable the MT 103 + format option only if you would like to generate outgoing MT 103 messages in the MT 103 + format.

If you are enabling this option for a specific currency, ensure to also enable this option:

- For your bank branch in the Branch Parameters Maintenance
- For the customer of the contract, in the BIC Code Maintenance
- For the product used by the contract, in the Product Preferences

Consequently, while processing transactions in the specified currency for such a customer, branch and product, for which the MT 103+ option is enabled, the system generates outgoing payment messages in the MT 103 + format.

---

#### Note

Since the system is also capable of processing incoming MT 103 messages in the MT 103 + format. Therefore, during the upload process for your branch, the system considers an

MT 103 payment message to be of MT 103+ format for those customer, currency and product combinations, for which the MT 103+ option has been enabled.

---

### **CLS currency**

To allow customers of your bank to settle their FX deals via the CLS (Continuous Linked Settlements) Bank, you can identify the currency to be a 'CLS Currency'. FX deals in the CLS currency only will be eligible to be routed through the CLS bank.

From the available list of CLS currencies, you can further maintain a list of 'allowed' or 'disallowed' currencies for a specific customer. Every customer who is a 'CLS Participant' will be allowed to trade in all the available CLS currencies unless specifically mentioned.

*Refer the 'Continuous Linked Settlements' chapter of the Foreign Exchange User Manual for details on maintaining currency restrictions and other maintenances required for processing CLS deals in Oracle FLEXCUBE.*

### **Index Flag**

Check this box to derive index rate of the currency in Lending module.

### **Validate Tag 50F**

Check this box to indicate that validations need to be performed for the 50F details captured for the ordering customer during contract input.

*For more details on 50F validations, refer the chapter titled 'Maintaining Addresses for a Customer' in Messaging System user manual.*

---

### **Note**

Customer cover messages are always generated in new format (MT202COV or MT205-COV).

---

*For more details on new cover message formats, refer settlements user manual.*

## **Indicating Rounding Preferences**

### **Rule**

This refers to the method to be followed for rounding off fractional units of a currency. The rounding preferences available are:

- Truncate — The amount is truncated to the number of decimals specified for the currency
- Round Up — The amount is rounded up based on the number of decimals and the nearest rounding unit
- Round Down — The amount is rounded down based on the number of decimals and the nearest rounding unit

For example,

<b>Amount before Rounding</b>	<b>Rounding Method</b>	<b>No. of Decimals</b>	<b>Rounding Unit</b>	<b>Amount after Rounding</b>
1234.678	Truncate	2	-	1234.67
1234.678	Round up to the nearest rounding unit	2	.01	1234.68

1234.678	Round down to the nearest rounding unit	2	.01	1234.67
----------	---	---	-----	---------

### Unit

If you have selected Round Up or Round Down in the Rule field, you need to indicate the nearest unit to which the rounding should take place. The number of units specified here should not be greater than the number of decimals allowed for the currency.

### Example

The decimal points specified for currency 'A' is 2. Rounding unit is .05

Amount for transaction is USD 100.326, which will be rounded off depending upon the decimals specified and the rounding rule and rounding unit.

For Rounding Rule 'Up', the amount available for transaction would be USD 100.35. For rounding rule 'Down', the transaction amount would have been rounded down to 100.30

If the rounding rule was specified as 'truncate' then, the amount would have rounded off to 100.32 (simply, knock off all decimal points beyond the stated decimals places to be rounded off). Thus whenever you specify a 'truncate' option you need not state the 'Rounding unit'.

### Specifying Amount Format Mask

Specify the format in which amounts in this currency are to be displayed for contracts in this currency. Two options are available:

999,999,999

9,999, 999, 99

The system defaults to the 999,999,999 format.

### **Euro Type**

When maintaining a currency in the Currency Definition screen, you have to specify the 'type' of the currency with relation to transition phase of the European Economic and Monetary Union (EMU). You can do this in the 'Euro Type' field.

Your specifications in this field enable you to handle the *first phase* of the EMU, which commenced on 01 January 1999.

*For more details on the manner in which Oracle FLEXCUBE handles the Euro, refer the chapter 'Handling the Euro'.*

By choosing the appropriate option, you can indicate if the currency is:

- The Euro
- An 'In' currency
- An 'Out' currency
- 'Euro Closed'

National currencies of 'In' countries are referred to as 'In' currencies. When maintaining other currencies, you have to choose the 'Out Ccy' option under Euro Type.


When the transition period ends, the national currencies of the participating countries would cease to exist as valid legal tenders. The Euro would be the only legal tender in the participating countries. Consequently, the Euro changes made to Oracle FLEXCUBE will no longer be required.

You can turn off the changes at the end of the transition period by:

1. Closing all 'In' currencies, and
2. Choosing the 'Euro Closed' option (for the Euro)

### 2.6.1.1 **PC Button**

Click 'PC' button in the Currency Definition screen to invoke 'Limits' screen.



Auto Exchange Rate \_\_\_\_\_  
Debit Auto Exchange Rate Limit \_\_\_\_\_  
Credit Auto Exchange Rate Limit \_\_\_\_\_

Ok Exit

You can specify the credit limit and the debit limit for the exchange rate in this screen. The transaction amount of a PC contract must not exceed the limit specified here.

---

#### **Note**

As PC remediated from ROFC, the system will not use these values anywhere even though you maintained the values in PC tab

---

### 2.6.1.2 **Currency Country Mapping Button**

Click 'Currency Country Mapping' button in the Currency Definition screen to invoke 'Clearing Zones Country Codes for Currency' screen.

The screen appears as shown below:

You can map a currency code to a country in this screen.

### **Currency Code**

The system displays the currency code maintained in the system.

### **Maintenance Country**

The system displays the maintenance country for the currency.

### **Maintenance Country Name**

The system displays the name of the country for which the currency is maintained.

### **Country Code and Description**

#### **Country Code**

Specify the clearing zone country code. Alternatively, you can select the country code from the option list. The list displays all the country codes maintained in the system.


#### **Country Name**

The system displays the name of the clearing zone country.

### **2.6.1.3 Fields Button**

You can associate values to all the User Defined fields created and attached to the Currency Definition Screen. You can view the list of User Defined fields associated by clicking the 'Fields' button.

The screen appears as shown below:



You can enter the value for the UDFs listed here in the 'Value' column.

*For more details on how to create user Defined fields, refer chapter 'Creating custom fields in Oracle FLEXCUBE' in the User Defined Fields User Manual under Modularity.*

#### 2.6.1.4 **Annexure**

The treatment for interest calculation varies with each of the interest calculation methods. Each method is dealt with individually below:

##### **Actual/Actual Method**

$$10,000 \times 10 / 100 \times (31 / 365 + 84 / 366)$$

In this method, the number of days is calculated as follows:

Dec. -31 days (include from date exclude to date)

Jan -31 days

Feb.-29 days (leap year)

March - 24 days (include from date exclude to date)

$$\text{Total} = 31 + (31 + 29 + 24 = 84) = 115$$

---

##### **Note**

When the interest period crosses from a non-leap year to a leap year (or otherwise), the basis of actual days has to be treated separately in each year.

---

Therefore, the denominator for the 31 days in December is 365 as it is a non-leap year and the denominator for the 84 days in 2000 is 366 as it is a leap year.

##### **Actual /365 Method**

$$10,000 \times 10 / 100 \times 115 / 365$$

In this method, the number of days is calculated as follows:

Dec. -31 days (include from date exclude to date)

Jan -31 days

Feb.-29 days (leap year)

March - 24 days (include from date exclude to date)

Total=31+31+29+24=115

**Actual/360 Method**

$10,000 \times 10 / 100 \times 115 / 360$

In this method, the number of days is calculated as follows:

Dec. -31 days (include from date exclude to date)

Jan -31 days

Feb.-29 days (leap year)

March - 24 days (include from date exclude to date)

Total=31+31+29+24=115

**30 Euro/Actual Method**

$10,000 \times 10 / 100 \times (30 / 365 + 84 / 366)$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 Euro Method, all months have 30 days, February included.)

Feb. - 30 days (In 30 Euro Method, February always has 30 days, leap year or not)

March - 24 days (include from date exclude to date)

Total = 113 days

---

**Note**

When the interest period crosses from a non-leap year to a leap year (or otherwise), the basis of actual days has to be treated separately in each year.

---

**30 Euro/365 Method**

$10,000 \times 10 / 100 \times 114 / 365$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 Euro Method, all months have 30 days, February included.)

Feb. - 30 days (In 30 Euro Method, February always has 30 days, leap year or not)

March - 24 days (include from date exclude to date)



Total = 113 days

**30 Euro/360 Method**

$10,000 \times 10 / 100 \times 114 / 360$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 Euro Method, all months have 30 days, February included.)

Feb. - 30 days (In 30 Euro Method, February always has 30 days, leap year or not)

March - 24 days (include from date exclude to date)

Total = 113 days

**30 US/Actual Method**

$10,000 \times 10 / 100 \times (30 / 365 + 84 / 366)$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 US Method, all months have 30 days, only for February are the actual number of days calculated.)

Feb. - 29 days (In 30 US Method, actual days are accounted for the leap year.)

March - 24 days (include from date exclude to date)

Total = 113 days

---

**Note**

When the interest period crosses from a non-leap year to a leap year (or otherwise), the basis of actual days has to be treated separately in each year.

---

**30US/365 Method**

$10,000 \times 10 / 100 \times 114 / 365$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 US Method, all months have 30 days, only for February are the actual number of days calculated.)

Feb. - 29 days (In 30 US Method, actual days are accounted for the leap year.)

March - 24 days (include from date exclude to date)

Total = 113 days

**30US/360 Method**

$10,000 \times 10 / 100 \times 114 / 360$

In this method, the number of days is calculated as follows:

Dec. - 30 days (include from date exclude to date)

Jan - 30 days (In 30 US Method, all months have 30 days, only for February are the actual number of days calculated.)

Feb. - 29 days (In 30 US Method, actual days are accounted for the leap year.)

March - 24 days (include from date exclude to date)

Total = 113 days

## 2.6.2 Maintaining Currency Position GL

You can maintain the currency position GL and position eqv GL in 'Currency Position GL Maintenance' screen. You can invoke this screen by typing 'CYDPOSSL' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a software window titled "Currency Position GL Maintenance". At the top, there is a menu bar with "New" and "Enter Query". Below the menu bar, there are four input fields with labels: "Maintenance Country \*", "Currency Code \*", "Position GL", and "Position Equivalent GL". The bottom of the window has a status bar with several fields: "Maker", "Checker", "Date Time", "Mod No", "Record Status", "Authorization Status", and an "Exit" button.

### **Maintenance Country**

Specify the country code for which the currency is maintained. Alternatively, you can select the country code from the option list. The list displays all the authorized and open country codes along with their description maintained in the system.

### **Currency Code**

Specify the currency code. Currencies are identified in Oracle FLEXCUBE by the SWIFT codes assigned to them. The currency will be identified by this code in all transactions that involve it.

### **Position or Position Equivalent GL for a currency**

If you have opted for position accounting in your bank, then you need to maintain the same using CYDPOSSL to indicate the Position GL and the Position Equivalent GL.

When maintaining GLs in your bank, you can opt to link different foreign currencies, associated with GL to either of the following:

- The Position GLs that you specify here (for the corresponding currency)
- Position GLs of your choice

### 2.6.3 Viewing Currency Summary Details

You can view currency summary details in the 'Currency Summary' screen. You can invoke this screen by typing 'CYSCDEFE' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

<input type="checkbox"/>	Authorization Status	Record Status	Currency Code	Currency Name	Currency Country	Decimals	Rule	Units	Spot days	Interest Method	Position GL	Position
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												
<input type="checkbox"/>												

In the above screen, you can base your queries on any or all of the following parameters and fetch records:

- Authorization Status
- Currency Code
- Record Status
- Maintenance Country

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Currency Code
- Currency Name
- Country
- Decimals
- Rule
- Units
- Spot days
- Interest Method
- Position GL
- Position Equivalent GL
- Maintenance Country

## 2.6.4 Maintaining Currency Pair

In the foreign exchange markets, the exchange rates for some currency pairs such as the USD-GBP or USD-JPY are easily obtainable, since these are frequently traded. The exchange rates of other currencies such as the ZAR-INR (South African Rand - Indian Rupee), which is not traded very often, is determined through a third currency. This third currency is usually the US dollar, since the US dollar is quoted in all trading centres.

In the Currency pair definition screen, you define the static attributes of currency pairs for which a regular market quote is readily available. For other pairs, which do not have a regular market quote, you need to specify the third currency through which the system should compute the exchange rate.

The currency pair screen is maintained at the bank level by your Head Office branch using the 'Currency Pair Maintenance' screen.

You can invoke this screen by typing 'CYDCCYPR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Currency Pair Maintenance

New

**Currency Pair**

Maintenance Country \* \_\_\_\_\_ Maintenance Country Name \_\_\_\_\_

Currency 1 \* \_\_\_\_\_ Currency Description \_\_\_\_\_

Currency 2 \* \_\_\_\_\_ Currency Description \_\_\_\_\_

Through Currency

**Through Currency**

Currency Code \_\_\_\_\_ Number Of Units  One  
 Hundred

Currency Name \_\_\_\_\_  Thousand

Quotation Method  Direct  Indirect Spread Definition  Percentage  Points

Points Multiplier 1.0000

Fields

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:		Authorization Status

Exit

### System Features

From among the currencies maintained in the currency screen, the system builds all possible combinations of currencies in pairs. For example, if you have maintained the following currency codes: USD, YEN. The system will give you a choice of defining parameters for the following pairs.

- USD-INR
- USD-YEN
- INR-USD
- INR-YEN
- YEN-USD
- YEN-INR

It is however, not obligatory to define parameters for all these pairs. A currency pair needs to be maintained only if:

- You want to define a direct exchange rate for the pair: for frequently traded currencies like INR-USD or USD-GBP or USD-JPY for which market quotes are available.
- You want to define a through currency for the pair: for those currencies which are not so well traded, market quotes may not be available. Therefore you can route the conversion rate for the pair via a 'through currency'. For example, in the case of GBP-NLG, for which a direct exchange rate may not be available, you can define a through currency say, USD. The exchange rate between GBP-USD and NLG-USD will be picked up by the system to compute the exchange rate between GBP-NLG.

In the absence of a direct exchange rate, the system will look for a through currency to compute the rate. If a 'through currency' has not been maintained then the default local currency will be picked up as the through currency to compute the rate for a currency pair.

## **Currency Pair**

### **Maintenance Country**

Specify the country code for which the currency pair is maintained. Alternatively, you can select the country code from the option list. The list displays all the authorized and open country codes along with their description maintained in the system.

For example, if you maintain the country code for a bank or a branch, which is operating in Singapore for the currency USD, then you should specify the country code as SG. The system defaults the field 'Country' as US.

### **Maintenance Country Name**

The system displays the name of the country for which the currency pair is maintained.

### **Currency Pair**

A currency pair (specified as Currency1 and Currency2, in the Currency Pair screen) represents the two currencies for which you need to maintain exchange rates.

To specify the pair, choose from the list provided against Currency1. Select the pair for which you want to maintain parameters.

The pair should be selected according to the quotation method followed by the market, which could be direct or indirect (for details refer to the field 'quotation method'). Exchange rates can be defined for currency1 against currency2 or currency2 against currency1.

The descriptions of the respective currencies are displayed below.

## **Through Currency**

If the exchange rate for a particular currency pair is not to be maintained, specify the 'Through Currency' via which the exchange rate between the currencies should be calculated.

To maintain a through currency for a currency pair, check against the box 'Through Currency'.

Then choose from the list codes provided against Code, Select the currency code, which you want to specify as the 'through currency'. The exchange rate for the currencies involved in the pair will be calculated using the through currency.

---

**Note**

- While maintaining a pair involving an 'In' currency ('In' – 'Out' and 'In' – 'In'), you can only specify the Euro as the 'Through Currency'. Please note that you cannot maintain a 'Through Currency' for a pair constituted by an 'In' currency and the Euro.
- 

*For more details on the manner in which Oracle FLEXCUBE handles the Euro, refer the chapter 'Handling the Euro' in this manual.*

Whenever, you define a through currency for a currency pair, you will not be allowed to specify the following for the pair:

- Number of units
- Spread definition

**Quotation Method**

This is the method to be followed for quoting the exchange rate. There are two methods direct and indirect.

In the Direct method the exchange rate for the currency pair is quoted as follows:

Buy rate = mid rate - buy spread

Sell rate = mid rate + sell spread

Ccy 1 = Rate x Ccy 2

In the Indirect method the exchange rate for the currency pair is quoted as follows:

Buy rate = mid rate + buy spread

Sell rate = mid rate - sell spread

Ccy 2 = Rate x Ccy 1

**Example**

The market follows the direct quote convention for the currency pair USD-DEM e.g., 1USD=1.6051DEM. To maintain this pair, you would specify currency 1 as USD and currency 2 as DEM, and specify "direct" in this field.

For the USD-GBP pair, which is quoted indirectly (1 GBP = 1, 5021 USD), the USD will be defined as currency 1 and the GBP as currency 2, with the quotation method "indirect".

**Number of Units**

This indicates the number of units of currency to be used for currency conversion

**Spread Definition**

You need to indicate the method in which the spread for a currency pair needs to be defined. There are two ways of defining the spread -- in points and in percentage.

The effective spread can be calculated using any of the following two methods:

- In points — spread x points multiplier
- In percentage — spread/100 x mid rate

The method of spread definition that you specify here applies to two instances:

- While maintaining exchange rates for this currency pair
- While maintaining Customer Spread for this currency pair

### 2.6.4.1 Specifying Points Multiplier

Points are the smallest unit of measurement in the exchange rate of a currency pair. If you have opted for a points system of defining spread, you should specify the multiplication factor for the points to compute effective spread.

Suppose for the currency pair USD-DEM your rates are as follows:

Mid-Rate:1.6045

Buy rate:1.6040

Sell rate:1.6051

The effective buy spread is 0.0005 (1.6045 - 1.6040) and the effective sell spread is 0.0006 (1.6051 - 1.6045).

In the Rates screen, where you define rates and spreads for a currency pair, you can specify the buy and sell spreads as 5 and 6 instead of as 0.0005 and 0.0006 (i.e., as spread points), and specify here the points multiplier as 0.0001.

The effective spread, buy and sell rates are then computed as follows:

Effective buy spread = Buy spread x Points multiplier = 5 x 0.0001 = 0.0005

Buy rate= Mid rate - Buy spread = 1.6045 – 0.0005 = 1.6040

### 2.6.5 Viewing Currency Pair Summary

You can view the summary details of currency pair in the 'Currency Pair Summary' screen. You can invoke this screen by typing 'CYSCCYPR' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Authorization Status	Record Status	Currency 1	Currency 2	Maintenance Country
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				
<input type="checkbox"/>				

In the above screen, you can base your queries on any or all of the following parameters and fetch records:

- Authorization Status
- Currency 1
- Record Status
- Currency 2
- Maintenance Country

Click 'Search' button. The system identifies all records satisfying the specified criteria and displays the following details for each one of them:

- Authorization Status
- Record Status
- Currency 1
- Currency 2
- Maintenance Country

## 2.6.6 Maintaining Currency Rate Type

You can maintain currency rate types in this screen.

You can invoke 'Currency Rate Type Maintenance' screen by typing 'CYDCRATY' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Specify the following fields

### **Type**

Specify the currency rate type.

### **Description**

The system displays the currency rate description.

## 2.6.7 Maintaining Currency Exchange Rates

In the Currency Rates screen, you can maintain exchange rates for a currency pair, the rates at which you buy and sell one currency for another.

A bank determines its buy and sell rate for a currency pair by applying a spread (i.e., its profit margin) to the mid-rate of the currency pair. Mid rate is the basic rate at which a currency pair is exchanged.

The spread applied for a currency pair varies with the transaction type, while the mid-rate usually remains constant. Consequently, different rates are applicable to different transaction types. For instance dollars in currency are purchased at a certain rate, while USD traveler's



checks are bought at a different rate. In Oracle FLEXCUBE, you can define a rate type which you would like to associate with a transaction type e.g., 'CASH', 'TRAVCHKS', etc., in the Rates screen.

In the Currency Rates Maintenance screen, you define the mid-rate, buy and sell spread applicable to each rate type; the buy and sell exchange rates are computed by the system.

Buy rates and sell rates can either be maintained by individual branches or can be input by the HO and propagated to all the branches.

If the flag 'Copy Exchange Rates to Branches' is set to Yes at 'Bank Parameter Level', then on authorization of exchange rate maintenance:

- If the branch for which the rate is being uploaded or maintained is the head office branch, then the rate would be copied to all those branches that have the same country code as the head office branch.
- If the branch for which the rate is being uploaded or maintained is not the head office branch, but it has the same country code as the head office branch, then the rate being uploaded or maintained would be specific to the branch and would not be copied to any other branch.
- If the branch for which the rate is being uploaded or maintained is not the head office branch and also does not have the same country code as the head office branch, then the rate being maintained would be copied to all the branches that has the same country code linked as the branch for which the rate is being maintained or uploaded.

In the Bank-wide Preferences screen, if you have not specified 'copy exchange rate to branches' then the 'Currency Exchange Rates Input' screen is maintained at the branch level by the different branches.

You can invoke this screen by typing 'CYDRATEE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button. The screen appears as shown below:

The screenshot shows the 'Currency Exchange Rates Input' window. At the top, there are two red-labeled input fields: 'Currency 1 \*' and 'Currency 2 \*'. Below them is a 'Branch Code' input field. A 'Currency Rate' section contains a table with the following columns: 'Rate Type \*', 'Mid Rate', 'Buy Spread', 'Sell Spread', and 'Buy Rate'. There are two rows in the table, both with empty cells. A 'Go' button is located to the right of the table. Below the table is a horizontal scrollbar. At the bottom of the window, there is an 'Enrich' button. The status bar at the very bottom contains the following fields: 'Maker', 'Checker', 'Date Time:', 'Date Time:', 'Mod No', 'Record Status', 'Authorization Status', and an 'Exit' button.

In this screen you maintain the following parameters for each rate type of a currency pair:

- Mid rate
- Buy spread and Sale spread
- Buy rate and Sale rate

### **Currency 1 and 2**

Specify the currency pair for which you want to compute the exchange rates. The list displays the currency pair that are maintained for the country to which the branch belongs.

The pair should be selected keeping in mind the quotation method for exchange rates as followed by the market. The system offers the choice of maintaining both the currencies as currency1 or currency 2 -- USD against DEM and DEM against USD.

For the pair specified the following parameters need to be maintained to arrive at the buy and sell rate of currencies:

- Rate Type
- Mid Rate
- Buy Spread
- Sell Spread

### **Rate Type**

This is the rate type for which you are maintaining exchange rates for a currency pair. For different transaction categories your bank would like to maintain different exchange rates. For example, traveller's check is purchased at a certain rate whereas a bill of exchange is bought at a different rate.

In the front-end-modules, where you define products to cater to the various transaction types of your bank, you can link an appropriate rate type to the product. For instance, you create a product to cater to outgoing cross currency transfers by SWIFT. For this product, if you define the rate type to be STANDARD then for all contracts linked to this product, the Standard Rate Type would be applied.

### **Mid Rate**

Mid rate is an indicative exchange rate for a currency pair. It is the average of the buy and sell rate quoted by the market for a currency pair.

For example,

currency 1 = USD

Currency 2 = INR

Buy rate -- 1 USD = 1.7020 INR

Sell rate -- 1 USD = 1.7040 INR

Mid-Rate = 1.7030

### **Buy Spread**

This is the buy spread for a currency pair. It can be defined as the profit margin specified over the mid rate when you buy currency 1 for currency2. You can define the buy spread in two ways -- either in points or in percentage. The system computes the effective buy spread for you.

### **Sale Spread**

This is the sell spread for a currency pair. It can be defined as the profit margin specified over the mid rate when you sell currency 1 for currency 2. You can define the sell spread either in points or in percentage. The system computes the effective sell spread for you.

### **Buy Rate**

Buy rate is the rate of exchange for a currency pair, which is computed by the system based upon the mid rate, the spread specified, the spread definition and the quotation method maintained in the 'Currency definition' screen.

### **Sale Rate**

Sell rate is the rate of exchange for a currency pair, which is computed by the system based upon the mid rate, the spread specified, the spread definition and the quotation method maintained in the 'Currency definition' screen.

You can also input the buy and sell rate for a currency pair. In which case, the system will compute the spread for the rate type.

### **Rate Date**

This is a display field. When you enter the exchange rate for a currency pair, the system will default the Rate Date as the Application Date. The rate date will always be less than or equal to the application date.

### **Rate Serial**

This is a running serial number for the Rate Date. You need to specify the serial number. Your entry will be validated for uniqueness. For example, there could be only one exchange rate between USD and EUR for 31/07/2003 with Rate Type STANDARD with Rate Serial as 0001. Thus, this will be a unique rate serial for a currency pair, rate type combination for a given rate date.

When you enter the exchange rate for a currency pair, the system will default the Rate Date as the Application Date and the Rate Serial as the latest available serial for the currency pair + 1. The Rate Serial Number will be system generated. However, you can modify it if required. This number takes into account the Rate Serial Number present in the Currency Rates History screen too. The Rate Serial Number and the Rate Date will be displayed during authorization of the Rate in the Currency Authorization screen.

## **2.6.7.1 Authorizing Exchange Rates**

Authorization of exchange rates is done from the Currency Exchange Rates input screen. Details like old value, new value for each field (buy rate, mid rate etc) are displayed. Click authorise icon to authorize the record.

## **2.6.7.2 Revising Exchange Rates**

For revising the exchange rates for your bank or the branches invoke the 'Currency Maintenance' screen. Click the currency pair whose exchange rate you want to revise and click unlock icon on the toolbar. Input/modify the new rates for the pair.

## **2.6.8 Viewing Exchange Rates**

You can view the exchange rates in the 'Currency Exchange Rates View' screen. You cannot input any values. You also have the option of specifying whether you want to view authorized rates or the unauthorized rates for any currency pair.

You can invoke this screen by typing 'CYSRATEE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screen appears as shown below:

The screenshot shows a web application window titled "Currency Exchange Rates View". At the top, there is a search bar with buttons for "Search", "Advanced Search", "Reset", and "Clear All". Below the search bar is a "Case Sensitive" section containing several input fields: "Authorization Status" (a dropdown menu), "Record Status" (a dropdown menu), "Branch Code", "Currency 1", and "Currency 2". Below these fields is a navigation bar with "Records per page" set to 15, "1 Of 1" records, and a "Go" button. To the right of the navigation bar is a "Lock Columns" dropdown menu set to 0. The main area of the screen is a table with columns for "Authorization Status", "Record Status", "Branch Code", "Currency 1", and "Currency 2". The table is currently empty. In the bottom right corner, there is an "Exit" button.

If the branches pick up the exchange rates maintained by the HO, then each time you invoke the 'currency view' screen from a branch it is advisable to update this screen with the latest rate input, from the HO. To do this, click on 'Refresh'. Refresh updates the screen with the last exchange rates input.

### 2.6.8.1 Currency Rate Notification

You can update the exchange rates in the screen or upload through XML or upload through generic interface. The system generates a notification on authorization of the modified exchange rates.

If the parameter 'Copy Exchange Rates to Branches' at bank parameter level is selected, then the rates will be populated and notifications will be generated in all the branches.

## 2.7 Currency Holiday Maintenance

This section contains the following topics:

- [Section 2.7.1, "Maintaining Currency Holiday Calendar"](#)
- [Section 2.7.2, "Steps to Define Currency Holidays"](#)
- [Section 2.7.3, "Defining Currency Holidays"](#)

### 2.7.1 Maintaining Currency Holiday Calendar

You need to maintain a yearly list of holidays, for the currencies, defined in the currency screen. This is done in the 'Currency Holiday Calendar' screen.

The system uses the information maintained in this screen to check whether any settlement, involving a foreign currency (in the foreign Exchange, Money market, Funds Transfer, Loans & Deposit modules) falls on that currency's holiday. If yes, then the system will display a message stating so, and ask the user for an override

For any schedule or contract maturing at a future date say, 5 years hence, you can input the future date, only if the calendar for that year has been maintained.

The currency holiday screen is maintained at the Bank Level by the Head Office

You can maintain holiday calendar for a currency in this screen. You can invoke the 'Currency Holiday Calendar Maintenance' screen by typing 'STDCCHOL' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.



Specify the following fields:

### **Currency code**

Specify the currency code. Alternatively, you can select the currency code from the option list. The list displays all valid currency codes maintained in the system.

### **Year**

Select the year.

In this screen, you can maintain a list of holidays for each of the currencies maintained in the 'currency screen', for any year between 1 AD and 4000 AD.

## **2.7.2 Steps to Define Currency Holidays**

To define currency holidays for a year, (for instance, for 2000) you have to do the following:

Building the calendar for the year

### **Step 1**

Select 'new' from the Actions menu in the Application tool bar or click new icon. A blank screen appears and the cursor moves to the field 'Year'

### **Step 2**

Enter the year -- 2000 or move to the year 2000 using the arrows

### **Step 3**

To build the calendar for the year, 2000 click on the 'Refresh' button. This button is called the 'refresh / build up' button because it builds the calendar for you

### **Step 4**

Select the currency for which you are defining holidays. Please note:

- On invoking the calendar of any year, you will notice that Saturdays and Sundays are marked as weekly holidays for the currency. This is the default setting of the system.
- For identification, the working days are marked in black and the holidays in red.

### **2.7.3 Defining Currency Holidays**

To define any other weekly holiday for the currency, other than the default, double click the day of the week, listed on the top row of the screen. For instance, if you double click 'F', all Fridays in the year would be marked as holidays.

To clear off the default weekly holidays — Saturdays and Sundays, double click on 'sa' and 's' written on the top row.

To define annual holidays, click on the particular date to mark the selected date as a holiday.

If you want to unmark a day specified earlier as a holiday, double click on it, once again. You will notice that the day gets marked in black.

## **2.8 Floating Rates Definition**

This section contains the following topics:

- [Section 2.8.1, "Invoking LD MM Floating Rate Input Screen"](#)
- [Section 2.8.2, "Invoking Rate Code Definition Screen"](#)
- [Section 2.8.3, "Capturing Currency Details"](#)
- [Section 2.8.4, "Specifying Effective Date and Amount Slab Details"](#)
- [Section 2.8.5, "Tenor and Interest Rate Details"](#)
- [Section 2.8.6, "Rate Code Usage"](#)

### **2.8.1 Invoking LD MM Floating Rate Input Screen**

The Interest Rate Type of a product can be one of the following:

- Fixed
- Floating
- Special

A Floating Rate corresponds to the market rates for the day. These rates are maintained and updated daily (or whenever they change) in the Floating Rates Table. The rates can be applied on a contract with or without a spread.

You can define Floating Interest Rates through the 'LD MM Floating Rate Input' screen. You can invoke this screen by typing 'CFDFLTRI' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

### Rate Code

Specify the rate code to identify the Floating Rate you are defining. Alternatively, you can select the rate code from the list of values. The list displays all valid rate codes maintained in the 'Rate Code Definition' Screen (CFDFRTCD)

## 2.8.2 Invoking Rate Code Definition Screen

A Rate Code identifies a set of rates defined for a combination of Currency, Amount Limit (optional), Tenor and Effective Date. You can define rate codes through the 'Rate Code

Definition' screen. You can invoke this screen by typing 'CFDFRTCD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a window titled "Rate Code Definition" with a standard Windows-style title bar (minimize, maximize, close buttons). Below the title bar is a menu bar with "New" and "Enter Query" options. The main area contains two input fields: "Rate Code \*" (with a red asterisk) and "Description". To the right of these fields is a "Rate Code Type" dropdown menu currently set to "RFR". At the bottom of the window is a status bar with several fields: "Maker" and "Checker" (with a sub-label "Checker" below it), "Date Time:" (with a sub-label "Date Time:" below it), "Mod No", "Record Status" (with a sub-label "Authorization Status" below it), and an "Exit" button on the far right.

### Rate Code

Specify a code to identify the Floating Rate you are defining. You can associate several currencies to the rate code and specify rates for each currency. While processing a contract, you need to indicate this code to make the rate applicable to the contract.

### Description

Specify a unique description for the rate code.

### Rate Code Type

Select the rate code type from the drop-down list. By default, the system displays the value as RFR which is used to maintain the RFR rate for the rate code. The following options are also available for selection in the drop-down list:

- Inflation - Used to maintain Inflation Index for the rate code
- Others - Used to maintain the rates other than RFR and Inflation. For example: IOBR



## 2.8.2.1 Viewing Rate Code Definition Summary

You can view the Rate Code Definition details using 'Rate Code Definition Summary' screen. You can invoke this screen by typing 'CFSFRTCD' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a web application window titled "Rate Code Definition Summary". At the top, there is a search bar with buttons for "Search", "Advanced Search", "Reset", and "Clear All". Below the search bar, there are two dropdown menus for "Authorization Status" and "Record Status", and two text input fields for "Rate Code" and "Description", each with a magnifying glass icon. Below these fields, there is a table with columns for "Authorization Status", "Record Status", "Rate Code", and "Description". The table is currently empty. At the bottom right, there is an "Exit" button.

This summary screen can be used to search for external systems which match the data specified for any of the following criteria:

- Authorization Status
- Record Status
- Rate Code
- Description

For each record fetched by the system based on your query criteria, the following details are displayed:

- Authorization Status
- Record Status
- Rate Code
- Description

## 2.8.3 Capturing Currency Details

Each Rate Code is associated with a currency. You can define rates for the same Rate Code in different currencies.

For example, you can have a Rate Code TERMDEP45 (with a description of Rates for a Term Deposit of 45 days). Thus, you can define a set of rates for contracts in U S Dollar and another set for contracts in Great British Pounds.

When you link a contract in US Dollars to the Rate Code TERMDEP45, the rates defined for this currency will be applied. Similarly, if the contract is in Great Britain Pounds, the rates defined for that currency will be applied.

## 2.8.4 Specifying Effective Date and Amount Slab Details

### Amount Slab

For a specific Rate Code and Currency combination, you can define an amount slab structure for application of interest rates. You should specify the upper limit of the slab to which a particular rate should be applied. A rate that has been defined for an Effective Date - Amount Slab combination will be applicable to an amount less than or equal to the specified amount. You can thus define interest rates for a slab structure.

Let us extend the example we discussed for Rates and Effective Dates to include amount limits.

Amount (USD)	Effective Date	Interest Rate
10,000	01 January '97	12.5%
50,000	01 January '97	13.0%
999.9 million	01 January '97	14.0%

If the rates have to be applied on 01 January '97, they will be picked up as follows:

- For a deposit with an amount less than or equal to USD 10, 000, the rate will be 12.5%.
- For a deposit with an amount greater than USD 10,000 and less than or equal to 50,000, the rate will be 13%.
- For a deposit with an amount greater than USD 50,000 and less than or equal to USD 999.9 millionth, the rate applied will be 14%.

---

### Note

Notice that a huge amount (999.9 million) has been given as the last amount limit. This denotes that after 50,000 there is no upper limit in the slab. Further, if the component amount is greater than the highest slab, the appropriate rate for highest amount slab will be applied. Similarly, if the component amount is lesser than the lowest amount slab, the appropriate rate for lowest slab will be applied.

---

### Effective Date

Each rate that you define for a Rate Code and Currency combination should have an Effective Date associated with it. This is the date on which the rate comes into effect. Once a rate comes into effect, it will be applicable till a rate with another Effective Date is given for the same Rate Code and Currency combination.

The following example illustrates this point:

Rate Code: TERMDEP45

Currency: US Dollar

Effective Date	Interest Rate
01 January '97	12.5%
14 January '97	12.0%
31 January '97	13.0%

These rates will be applicable as follows:

Period	Interest Rate
01 January to 13 January '97	12.5%
14 January to 30 January '97	12.0%
31 January to one day before the next date	13.0%

---

**Note**

The rates will be applied to a contract depending on whether it has been defined with Auto Rate Code Usage or Periodic Rate Code Usage. You can specify this in the Product ICCF Details screen.

---

**Borrow/Lend Rate Indication**

For every Amount Limit - Effective Date combination, you should define the rate to be applied as a borrow rate or a lend rate. You also have the option to specify the mid rate.

**2.8.5 Tenor and Interest Rate Details**

The rates that will be applied for a given combination of Amount Slab – Effective Date – Lend/Borrow Indication can be tenor based. In the table, you can define tenors and indicate the rates applicable to each tenor. The rate will be applied to contracts based on the slab into which it falls and the reset tenor defined for the component.

**2.8.6 Rate Code Usage**

If you specify Auto Rate Code usage, all the rate changes made during the liquidation or accrual period will be considered. If you specify periodic rate code usage, the rates will be periodically refreshed and the rates as of a specific frequency will be applied.

This frequency is specified in the Contract Schedules screen while the Rate Code Usage is specified in the Product ICCF Details screen. The following example illustrates the concept:

For example, you have a deposit that has a Start Date as 1 October 1997 and a Maturity Date as 30 November 1997. The interest payment frequency is to be monthly. The contract has been defined with a floating rate.

The rates in the floating rate table change in the following manner:

Effective Date	Rate
1 October '97	12
12 October '97	11.5
25 October '97	11
15 November '97	12
30 November '97	12.5

If you want the floating rates to be applied automatically every time they change, you should specify Auto Rate Code usage in the Product ICCF screen. When you do this, if the first

interest payment is to be done on 31 October, all the rate changes between 1 October and 31 October will be considered automatically.

The rates will be applied for the number of days for which they remained unchanged in the rate table, as follows:

From	To	Rate
1 October	11 October	12
12 October	24 October	11.5
25 October	31 October	11

If you want the floating rates to be refreshed periodically, you should first specify the rate code usage as periodic, through the Product ICCF Details screen.

Next, you should define the rate revision schedules to specify when these rates should be applied on the deposit (that is, the frequency at which rates should be refreshed).

To do this, through the Contract Schedules screen, mark the component as a revision schedule by checking the Rev box. Then, specify the component (for example, INTEREST). Specify the frequency at which the interest rate has to be refreshed, say every fortnight. Specify the Start Date as, say, 15 October. That is, for a deposit defined with periodic rate code application, the rates prevailing on the dates at the frequency you have specified will be used for accruals and liquidation.

In the deposit we are discussing, with the frequency at which the rates should be refreshed defined as fortnightly and the Start Date as 15 October, the rate applied for the payment on 31 October will be as follows:

From	To	Rate
1 October	15 October	11.5
16 October	31 October	11

---

**Note**

Rev schedules are applicable only for contracts where the Rate Type is Floating and the Code Usage is Periodic. If the Code Usage is Automatic the system applies the effective rate whenever the underlying Rate gets updated.

---

## 2.9 External Entities Maintenance

This section contains the following topic:

- [Section 2.9.1, "Maintaining External Chart of Accounts"](#)
- [Section 2.9.2, "Maintaining External Transaction Code"](#)
- [Section 2.9.3, "Maintaining External Credit Approval"](#)
- [Section 2.9.4, "Maintaining External Customer Input"](#)
- [Section 2.9.5, "Viewing External Customer Summary"](#)
- [Section 2.9.6, "Maintaining External Customer Account"](#)
- [Section 2.9.7, "Mapping External Multi Currency Accounts"](#)

- [Section 2.9.8, "Maintaining External Consumer Loan Account"](#)

## 2.9.1 Maintaining External Chart of Accounts

You can invoke 'External Chart of Accounts' screen by typing 'STDCRGLM' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

You can specify the following fields:

### **GL Code**

Specify a code for the General Ledger.

### **General Ledger Description**

Specify a description for the General Ledger code.

### **GL Category**

Select the category of the General Ledger from the drop-down list. The list displays the following values:

- Asset
- Liability
- Income
- Expense
- Contingent Asset
- Contingent Liability
- Memo
- Position
- Position Equivalent

### **Blocked**

Check this box to block the GL for accounting entries.

### **Source System**

Specify the source system.

### **Posting Restrictions**

Indicates whether the General Ledger Code has Direct Posting or Indirect Posting.

## 2.9.2 Maintaining External Transaction Code

You can invoke 'External Transaction Code Maintenance' screen by typing 'STDCRTRN' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a software window titled "External Transaction Code Maintenance". At the top left, there is a "New" button. Below it, there are four input fields with labels: "Transaction Code \*", "Description", "Source System", and "Source Transaction Code". The bottom of the window features a light blue footer area with several fields: "Maker", "Checker", "Date Time:", "Date Time:", "Mod No", "Record Status", and "Authorization Status". An "Exit" button is located in the bottom right corner of this footer area.

You can specify the following fields:

### **Transaction Code**

Specify the transaction code of the external transaction.

### **Transaction Code Description**

Specify the description of the transaction code.

### **Source System**

Specify the source system of the transaction code.

### **Source Transaction Code**

Specify the source of the transaction code.

## 2.9.3 Maintaining External Credit Approval

You can invoke 'External Credit Approval System' screen by typing 'STDECAMT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a software window titled "External Credit Approval System". At the top left, there are two buttons: "New" and "Enter Query". Below them, there are two input fields with labels: "Source System" and "Description". The bottom of the window features a light blue footer area with several fields: "Maker", "Checker", "Date Time:", "Date Time:", "Mod No", "Record Status", and "Authorization Status". An "Exit" button is located in the bottom right corner of this footer area.

You can specify the following fields:

### **Source System**

Specify the source system.

## Description

Specify the description of the source system.

### 2.9.4 Maintaining External Customer Input

You can invoke 'External Customer Input' screen by typing 'STDCIFCR' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows the 'External Customer Input' application window. The window title is 'External Customer Input' and it has a menu bar with 'New' and 'Enter Query'. The form contains several input fields: 'Customer No \*', 'Source System Customer \*', 'Source System \*', 'Short Name', 'Customer Type' (with radio buttons for Individual, Corporate, and Bank), 'Customer Name', 'Address Line 1', 'Address Line 2', 'Address Line 3', 'Address Line 4', 'Country', and 'Language'. On the right side, there are fields for 'Nationality', 'RM Id', 'Pin Code', 'Sanction Check Required' (checkbox), and 'Access Group' (with a 'Staff' option). At the bottom, there is a status bar with fields for 'Maker', 'Checker', 'Date Time:', 'Mod No', 'Record Status', and 'Authorization Status', along with an 'Exit' button.

You can specify the following fields:

#### Customer Number

Specify the customer number.

#### Source System Customer

Specify the Source System customer.

#### Source System

Specifies the source system.

#### Short Name

Specifies the short name of the customer.

#### Customer Type

Select the required type of customer. Choose any of the following:

- Individual - Click this button if the customer is an individual customer.
- Corporate - Click this button if the customer is a corporate customer.
- Bank - Click this button if the customer is a bank employee.

#### Customer Name

Specifies the name of the Customer.

#### Address Line 1

Specify the first line of the customer's address.

#### Address Line 2

Specify the second line of the customer's address.

**Address Line 3**

Specify the third line of the customer's address.

**Address Line 4**

Specify the fourth line of the customer's address.

**Pin code**

Specifies the pin code of the customer's address.

**Country**

Select the country of the customer's address.

**Language**

Select the language of customer's preferred language of communication.

**Nationality**

Specify the nationality of the customer.

**RM ID**

Specify the relationship id of the customer's relationship manager.

**Pin Code**

Specify the Pin Code.

**Access Group**

Specify the access group. Alternatively, you can select the access group from the option list. The list displays all valid access group maintained in 'Customer Access Group Maintenance' screen (STDACGRP).

**Staff**

Check this box to indicate whether the customer is a staff of the bank.

---

**Note**

When you try viewing details of a customer whose data is forgotten, the system displays an error message.

*For more information on forgetting customers refer Core Services - Security Management System user guide.*

---



## 2.9.5 Viewing External Customer Summary

You can view the uploaded data in the 'Customer Summary' screen. You can invoke the 'Customer Summary' screen by typing 'STSCIFCR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Customer Summary

Search Advanced Search Reset Clear All

Case Sensitive

Authorization Status  Record Status

Customer No  Customer Type

Customer Name  Short Name

Customer Category  Country

Nationality  Address Line 1

Records per page 15 1 Of 1 Go Lock Columns 0

Authorization Status	Record Status	Customer No	Customer Type	Customer Name	Short Name	Customer Category	Country	Nation
----------------------	---------------	-------------	---------------	---------------	------------	-------------------	---------	--------

Exit

The query option is available on the following fields in this screen:

- Authorization Status
- Record Status
- Customer No.
- Customer Type
- Customer Name
- Short Name
- Customer Category
- Country
- Nationality
- Address Line 1
- Source System Customer
- Source System

---

### Note:

When you try viewing details of a customer whose data is forgotten you see a message saying that no record exists.

---

*For more information on forgetting customers refer Core Services - Security Management System user guide.*

## 2.9.6 Maintaining External Customer Account

You can invoke 'External Customer Account' screen by typing 'STDCRACC' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

External Customer Account Input

New Enter Query

Host Code \_\_\_\_\_ Account Class Normal Account

Customer Account \* \_\_\_\_\_ Customer Name \_\_\_\_\_

Customer Number \* \_\_\_\_\_ Address Line 1 \_\_\_\_\_

Account Currency \_\_\_\_\_ Address Line 2 \_\_\_\_\_

Account Name \* \_\_\_\_\_ Address Line 3 \_\_\_\_\_

Account IBAN \_\_\_\_\_ Address Line 4 \_\_\_\_\_

External Credit Approval System \*  External Credit Approval Required

Source Account Branch \* \_\_\_\_\_ Payment Entitlement Group \_\_\_\_\_

Source Customer Account \* \_\_\_\_\_ Branch Entitlement Group \_\_\_\_\_

Country \_\_\_\_\_

Maker Date Time: Mod No Record Status

Checker Date Time: Authorization Status

Exit

You can specify the following fields:

### Host Code

Specify the Host Code that is linked to the logged in user of the branch.

### Customer Account

Specify the customer account number.

### Customer Number

Specify the required customer number. Alternatively, you can select the customer number from the option list. The list displays all valid customer numbers maintained in the system.

### Account Currency

Specify the required currency of the external customer. Alternatively, you can select the currency from the option list. The list displays all valid currencies maintained in the system.

### Account IBAN

Specify the IBAN that is linked to the customer.

### Account Name

Specify the name of the Account holder.

### External Credit Approval System

Specify the External Credit Approval System for which accounts are mapped. Alternatively, you can select the ECA from the option list. The list displays all valid ECA systems maintained in the system.

### Source Account Branch

Specify the Source Account Branch.

### Source Customer Account

Specify the Source Customer Account.

**Country**

Specify the Country.

**Account Class**

Select the required account class of the external customer account. Choose between the following:

- Normal Account
- Nostro Account
- Multi Currency Account

The account currency should be null if account class is selected as multi currency account. The system throws an error message if the account class is selected as multi currency account and the account currency is specified.

**Customer Name**

Specifies the name of the Customer.

**Address Line 1**

Specify the first line of the customer's address.

**Address Line 2**

Specify the second line of the customer's address.

**Address Line 3**

Specify the third line of the customer's address.

**Address Line 4**

Specify the fourth line of the customer's address.

**External Credit Approval Required**

Check this box to indicate that ECA check is required for the external customer account.

**Payment Entitlement Group**

Specify the payment entitlement group. The adjoining list displays all valid payment entitlement groups maintained in the Customer Account Entitlement Group Maintenance Screen (STDCRAEG).

**Branch Entitlement Group**

Specify the branch entitlement group. The adjoining list displays all valid branch entitlement groups maintained in the Customer Account Entitlement Group Maintenance Screen (STDCRAEG).

---

**Note**

When you try viewing details of a customer whose data is forgotten, the system displays an error message.

*For more information on forgetting customers refer Core Services - Security Management System user guide.*

---

## 2.9.7 Mapping External Multi Currency Accounts

You can map multi currency accounts and their currency with real accounts using 'External Multi Currency Account Mapping' screen. You can invoke this screen by typing 'STDCRMCA' in the top right corner of the Application toolbar and clicking the adjoining arrow button.

The screenshot shows a software window titled "External Multi Currency Account Mapping". At the top left, there is a "Save" button. Below it, there are four input fields: "Multi Currency Account \*", "Sub Account Number \*", "Primary Account" (with a checkbox), and "Currency \*". At the bottom, there is a status bar with fields for "Maker", "Checker", "Date Time", "Mod No", "Record Status", and "Authorization Status", along with a "Cancel" button.

You can maintain the following in this screen:

### Multi Currency Account

Specify the multi currency account. Alternatively, you can select the multi currency account from the option list. The list displays all the external multi currency accounts.

### Sub Account Number

Specify the sub account number.

### Primary Account

Check this box to indicate that the selected sub account number is the primary account. You can mark only one account under a multi currency account as primary account.

### Currency

Specify the currency of the sub account number. Alternatively, you can select the currency from the option list. The list displays all valid currencies maintained in the system.

## 2.9.8 Maintaining External Consumer Loan Account

You can capture consumer loan account details in the 'External Consumer Loan Account Input' screen. You can invoke this screen by typing 'STDCRCLN' in the top right corner of the Application toolbar and clicking the adjoining arrow button.

The screenshot shows a software application window titled "STDCRCLN\_Desc". At the top left, there are buttons for "New" and "Enter Query". The main area contains a form with the following fields and labels:

- Host Code
- Loan Account Number \*
- Loan Account Branch
- Customer Number \*
- Account Currency
- Account IBAN
- Account Status (with a dropdown menu showing "Active")
- Alternate Account Number
- Loan Account Class
- Source System \*
- Source Account Branch \*
- Source Loan Account \*

At the bottom of the window, there is a status bar with the following fields and labels:

- Maker
- Checker
- Date Time
- Mod No
- Record Status
- Authorization Status
- Exit (button)

Specify the following details:

### Host Code

Specify the host code of the external consumer loan account.

### Loan Account Number

Specify the consumer loan account number.

### Loan Account Branch

Specify the consumer loan branch.

### Customer Number

Specify the customer number of the external consumer loan account.

### Account Currency

Specify the currency of external consumer loan account.

### Account IBAN

Specify the IBAN of external consumer loan account.

### Account Status

Select the account status from the drop-down list. The list displays the following options:

- A-Active
- Y-Inactive
- L-Liquidated
- R- Reversed

### Alternate Account Number

Specify the alternate account number consumer loan account.

### Loan Account Class

Specify the loan account class.

### Source System

Specify the source system.

### Source Account Branch

Specify the source system account branch.

### Source Loan Account

Specify the source loan account.

## 2.10 External Limit Entities Maintenances

This section contains the following topics:

- [Section 2.10.1, "Maintaining External Collaterals"](#)
- [Section 2.10.2, "Maintaining External Collateral Pools"](#)
- [Section 2.10.3, "Maintaining External Facilities"](#)
- [Section 2.10.4, "Maintaining External Liability Linkage"](#)
- [Section 2.10.5, "Maintaining External Liability"](#)

### 2.10.1 Maintaining External Collaterals

You can maintain external collateral details in 'External Collateral Maintenance' screen. You can invoke this screen by typing 'STDCRCOL' in the top right corner of the Application toolbar and clicking the adjoining arrow button.

The screenshot displays the 'External Collateral Maintenance' application window. At the top, there are 'New' and 'Enter Query' buttons. The main area is titled 'Collateral Details' and contains the following fields:

- Host Code
- Liability No \*
- Customer No
- Collateral Code \*
- Collateral Description
- Collateral Currency \*
- Collateral Value \*
- Limit Contribution
- Start Date \* (format: YYYY-MM-DD)
- End Date (format: YYYY-MM-DD)
- Liability Name
- Source Laib ID
- Source Collateral Code
- Taken Over
- Source System

On the right side, there are additional fields:

- Branch Code \*
- Available
- Collateral Type (dropdown menu)
- Interest Rate

At the bottom, there is a 'Fields' section with the following labels: Maker, Checker, Date Time, Date Time, Mod No, Record Status, Authorization Status, and an 'Exit' button.

You can specify the following in this screen:

#### Collateral Details

##### Host Code

Specify the host code. Alternatively, you can select the host code from the option list. The list displays all valid values.

**Branch Code**

Specify the branch code in which the collateral is created.

**Available**

This check box will be checked by default, indicating that the collateral is available for linking to the collateral pool. You can uncheck this so as to manually freeze this collateral.

**Liability No**

Specify the liability Number for which the collateral is linked.

**Customer No**

Specify the customer number. Alternatively, you can select the customer number from the option list. The list displays all valid values.

**Collateral Code**

Specify the Collateral Code here. A maximum of 20 alphanumeric characters are allowed in this field. There should be only one Collateral code for a given Liability.

**Collateral Description**

Give a brief description of the collateral here.

**Collateral Type**

Indicate the type of collateral. The options are

- Property
- Vehicle
- Marketable Securities
- Plant and Machinery
- Precious Metal
- Guarantee
- Miscellaneous
- Policy

**Interest Rate**

Specify the interest rate of the collateral.

**Collateral Currency**

Specify the currency in which the Collateral has to be maintained. Once authorized you cannot change this entry.

**Collateral Value**

The collateral value depends on whether the security is Market Value based or Non-Market Value based.

If it is market value based then the collateral value is calculated as shown in the following examples.

Example

Input in case of a nominal quoted security:

Nominal Amount	Price Code	Market Price	Collateral Value [(Market price/100) * Nominal Amount]
10,00,000	BOM1	65	$(65/100) * 10,00,000=650000$

5,00,000	BOM2	70	$(70/100) * 5,00,000 = 350000$
7,00,000	BOM3	80	$(80/100) * 7,00,000 = 560000$

Input in case of a unit quoted security:

Number of Units	Price Code	Market Price	Collateral Value (Number of Units x Market price)
65	BOM1	120	7800
70	BOM2	130	9100
40	CAL1	95	3800

If it is Non-Market Value based then the user has to enter the collateral value manually.

### Limit Contribution

Specify the final amount contribution that will be applicable for a Limit.

Example

Collateral is valued at \$1000, and you wish to offer the customer credit only worth \$ 980. This amount is 98% of the collateral contribution.

$(1000 - 980) / 1000 = 2\%$  is the Hair cut percentage

This means you want to have a lendable margin of 98%.

For instance, if you enter the lendable margin percentage, then based on the value you enter, the hair cut will be calculated as described above and the limit contribution will be calculated.

### Start Date and End Date

Specify the tenor of the collateral using the Start Date and End Date fields. The collateral is considered effective only during this period.

The start date indicates the date from which the collateral becomes effective. The end date that you specify indicates the date on which the collateral ceases to exist. On the end date, the credit limit, of the credit line backed by the collateral, will be reduced by the amount that the collateral contributes to the credit line.

### Liability Name

Specify the liability name.

### Source Liab ID

Specify the source liability ID.

### Source Collateral Code

Specify the source collateral code.

### Taken Over

Taken Over collateral is checked if the collateral linked to CI/CL account is taken over.

### Source System

Specify the source system. Alternatively, you can select the source system from the option list. The list displays all valid options.



## 2.10.2 Maintaining External Collateral Pools

You can maintain external collateral pools in 'External Collateral Pools Maintenance' screen. You can invoke this screen by typing 'STDCRPOOL' in the top right corner of the Application toolbar and clicking the adjoining arrow button.

The screenshot shows the 'External Collateral Pools Maintenance' application window. The window title is 'External Collateral Pools Maintenance'. Below the title bar is a menu bar with 'New' and 'Enter Query'. The main area contains several input fields: 'Host Code', 'Liability No \*', 'Liability Name', 'Pool Code \*', 'Pool Description', 'Pool Currency \*', 'Pool Amt \*', 'Source Laib ID', 'Source Pool Code', 'Source System', 'Liability Branch', and 'Branch Code'. At the bottom, there is a 'Fields' section with columns for 'Maker/Checker', 'Date Time', 'Mod No', 'Record Status/Authorization Status', and an 'Exit' button.

You can specify the following in this screen:

### Host Code

Specify the host code. Alternatively, you can select the host code from the option list. The list displays all valid values.

### Liability No

Specify the liability to which the collaterals need to be linked.

### Liability Branch

The system displays the liability branch.

### Liability Name

Specify the liability name.

### Branch Code

The branch code for the branch where the collateral is maintained in the 'External Collateral Maintenance' screen gets defaulted here.

### Pool Code

Specify the Pool Code here. The pool code assigned to each collateral pool can be linked to a Liability while creating credit limits.

### Pool Description

Specify a brief description of the collateral pool here.

### Pool Currency

Specify the currency in which the Collateral Pool has to be maintained.

### Pool Amt

The system computes and displays the utilization amount to the Collateral Pool, if a collateral Pool is attached to a contract or account and not through a facility.

### Source Liab ID

Specify the source liability ID.

### Source Pool Code

Specify the source pool code.

### Source System

Specify the source system. Alternatively, you can select the source system from the option list. The list displays all valid options.

## 2.10.3 Maintaining External Facilities

You can maintain external facilities in 'External Facilities Maintenance' screen. You can invoke this screen by typing 'STD CRFAC' in the top right corner of the Application toolbar and clicking the adjoining arrow button.

The screenshot shows the 'External Facilities Maintenance' application window. The window title is 'External Facilities Maintenance'. The interface includes a 'New' button and an 'Enter Query' field. The main area contains several input fields: Host Code, Branch, Liability No (marked with a red asterisk), Liability Name, Line Code (marked with a red asterisk), Serial No (marked with a red asterisk), Description, Line Currency (marked with a red asterisk), Source Line Code, Source Line Serial, Source Liab ID, and Source System. To the right, there are checkboxes for 'Revolving Line', 'Unadvised', and 'Bulk PMT Required'. Below these is a 'Utilization Tracking' section with radio buttons for 'Local' and 'Global'. A section titled 'Amounts' contains 'Block Amount', 'Collateral Contribution', 'Limit Amount Basis' (with a dropdown menu showing 'Limit Amount + Collateral Contribution'), 'Limit Amount' (marked with a red asterisk), 'Transfer Amount', and 'Effective Line Amount'. At the bottom, there are fields for 'Maker/Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status', along with an 'Exit' button.

You can specify the following here:

### Host Code

Specify the host code. Alternatively, you can select the host code from the option list. The list displays all valid values.

### Branch

Specify the facility branch. Alternatively, you can select the branch code from the option list. The list displays all valid values.

### Liability No

Specify the Liability number here. Alternatively, you can select the liability number from the option list. The list displays all valid values maintained in the system.

### Liability Name

Specify the liability name.

### Line Code

Specify the Line Code to which the liability ID is to be associated with. Allocating credit limits for the Line-Liability combination can be done. The customer(s) who fall under this Liability Code will in turn avail credit facilities under this Credit line.

By linking a Credit Line to a Liability code the customer also gets linked to the Credit Line. This is true because a Liability code has been assigned to every credit seeking customer and the credit facilities granted to the customer are defined and tracked against this code.

**Serial No**

Each time a customer - line code combination is specified, LCM module assigns a unique serial number to the combination. This serial number is unique to the line-liability code combination. Thus, for every new record entered for a Line-Liability combination, a new serial number is generated. The Line - Liability - Serial number forms a unique combination.

**Description**

Give a brief description of the facility here.

**Line Currency**

Specify the currency in which the facility is defined. The currency that has been selected will have the following implications:

- The limit amount that has been specified for this Line-Liability combination is taken to be in this currency.
- The line that has been defined will be available for Utilization only in the line currency, unless specified otherwise under Currency Restrictions in this screen.

Once the entry is authorized you cannot change the currency.

If the limit allotted to this Line-Liability combination can be utilized by accounts and transactions in currencies other than the limit currency, the limit utilization will be arrived at by using the mid rate for the currency pair as of that day.

**Source Line Code**

Specify the source line code.

**Source Line Serial**

Specify the source line serial.

**Source Liab ID**

Specify the source liability ID.

**Source System**

Specify the source system. Alternatively, you can select the source system from the option list. The list displays all valid values.

**Revolving Line**

Select this check box to indicate that the credit line is revolving. A revolving credit line indicates that a repayment of the utilized credit should reinstate the credit limit of the customer.

**Unadvised**

Select this check box if the Liability is unadvised.

**Bulk PMT Required**

Check this box to indicate that bulk PMT is required.

**Utilization Tracking**

It signifies if the utilization tracking of the facility is done locally or globally.

## **Amounts**

### **Block Amount**

Specify the block amount.

### **Collateral Contribution**

The collateral amount which has been maintained is displayed when a collateral code has been picked.

### **Limit Amount Basis**

The value for Limit Amount can be maintained as the following:

- Limit Amount Basis
- Limit Amount + Collateral Contribution Limit Amount
- Min (Limit Amount, Collateral Contribution)

### **Limit Amount**

Specify the limit for the facility. If you have maintained schedules for limits, the system automatically updates the limit amount here on the dates specified for each limit in the schedule.

### **Transfer Amount**

System displays the transfer amount resulting from 'Facilities Amount Transfer' transactions. The value displayed has either the sign "-" or "+", indicating whether the amount is transferred from or to the line. If the sign is "-", then the amount is transferred from the line and if it is "+", then the amount is transferred to the line.

### **Effective Line Amount**

The system displays the effective line amount.

## **Availability**

### **Line Start Date**

Specify the line start date. If not specified, system defaults the line start date as the current application date.

### **Availability Flag**

If the Line facility is available then this check box will be checked.

### **Line Expiry Date**

The system displays line final expiry date. This is derived by adding the line grace days with the line expiry date. If 'Line Grace Days' is null, then system considers the limit expiry date as the final expiry date.

## **Facility Fee Preference**

### **Interest Required**

Select this check box to indicate the facility is applicable for interest calculation.

### **Interest Calc AC**

Specify the interest calculation account. Alternatively, you can select the interest calc account from the option list. The list displays all valid values.

## 2.10.4 Maintaining External Liability Linkage

You can link customers to liabilities using the 'External Liability Linkage Maintenance' screen. You can invoke this screen by typing 'STDCRLIK' in the top right corner of the Application toolbar and clicking the adjoining arrow button.

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:		Authorization Status

You can specify the following in this screen:

### Host Code

Specify the host code. Alternatively, you can select the host code from the option list. The list displays all valid values.

### Branch Code

The system defaults the branch code.

### Customer No

Specify customer's number to whom the liability has to be linked.

### Liability No

Specify the liability number. Alternatively, you can select the liability number from the option list. The list displays all valid values.

### Liability Name

Specify the liability name.

### Source Liab ID

Specify the source liability ID.

### Source Customer No

Specify the source customer number.

### Source System

Specify the source system. Alternatively, you can select the source system from the option list.

## 2.10.5 Maintaining External Liability

You can maintain liability details in 'External Liability Maintenance' screen. You can invoke the screen by typing 'STDCRLIB' in the top right corner of the Application toolbar and clicking the adjoining arrow button.

Fields					
Maker	Date Time:	Mod No	Record Status		
Checker	Date Time:		Authorization Status		Exit

You can specify the following in this screen:

### Host Code

Specify the host code. Alternatively, you can select the host code from the option list. The list displays all valid values.

### Liability No

Specify the Liability Number. If the Liability Number is customer group then all customers under this group should have same Liability Number.

### Liability Name

Specify the Liability Number. If the Liability Number is customer group then all customers under this group should have same Liability Number.

### Liability Branch

Specify the branch in which liability is associated.

### Liability Currency

Specify the currency with which the liability is associated. If Liability currency is different from Limit currency specified in Global Exposure Parameter then the Liability amount is converted to the limit currency.

### Overall Limit

Specify the overall limit amount for that liability. Value entered in the field will be in the currency stated above. If liability is of customer group then overall limits stated will be common to all the customers.

### Revision Date

Specify the date on which your bank would wish to revise the limit for the liability. The limit check will continue irrespective of the date maintained here. The revision date must be greater than the start date and can also be left blank.

### **Credit Rating**

The primary credit rating maintained in the credit rating sub screen is displayed here.

### **Source Liab No**

Specify source liability number.

### **Source System**

Specify the source system. Alternatively, you can select the source system from the option list. The list displays all valid values.

## **2.11 Settlement Details Maintenance**

This section contains the following topic:

- [Section 2.11.1, "Capturing the BIC Code Details"](#)
- [Section 2.11.2, "Viewing BIC Codes"](#)
- [Section 2.11.3, "Associating Customer to a BIC Code"](#)
- [Section 2.11.4, "Viewing Customer BIC Codes"](#)
- [Section 2.11.5, "Operations on a BIC Record"](#)
- [Section 2.11.6, "Maintaining Local Payments Bank Directory"](#)
- [Section 2.11.7, "Viewing Local Payments Bank Directory Details"](#)
- [Section 2.11.8, "Maintaining Bank Directory Plus"](#)
- [Section 2.11.9, "Viewing Bank Directory Plus Details"](#)
- [Section 2.11.10, "Maintaining IBAN Plus"](#)
- [Section 2.11.11, "Viewing IBAN Plus Details"](#)
- [Section 2.11.12, "Maintaining BICPlusIBAN"](#)
- [Section 2.11.13, "Viewing BICPlusIBAN"](#)
- [Section 2.11.14, "Maintaining IBAN Information"](#)
- [Section 2.11.15, "Viewing IBAN Information"](#)
- [Section 2.11.16, "Uploading BIC Files "](#)
- [Section 2.11.17, "IS File Upload"](#)
- [Section 2.11.18, "BIC Record File Formats"](#)
- [Section 2.11.19, "Local Bank Directory View"](#)

### **2.11.1 Capturing the BIC Code Details**

As part of setting up some basic information for the functioning of Oracle FLEXCUBE, you should maintain Bank Identifier Codes (BIC).

You can define bank codes through the 'BIC Code Details' screen. You can invoke this screen by typing 'ISDBICDE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button. If you are maintaining details of a new bank code, select 'New' from the Actions Menu in the Application toolbar or click new icon.

Customer BIC Codes can be maintained manually or uploaded from an external source onto Oracle FLEXCUBE.

#### **BIC Code**

You need to indicate the code by which the bank is identified by SWIFT. On indicating the Bank Identifier Code, you should indicate the detailed name of the bank. If the bank is not a customer of your bank, you will have to manually enter the name and address of the bank.

---

**Note**

The country information is captured to enable Mantas to analyse the transactions for possible money laundering activities.

---

*For more details on Mantas, refer 'Mantas' interface document.Sub-Type Code*

Select the appropriate sub-type code to be mapped to the BIC. The adjoining option list offers the following factory-shipped codes:

- BANK - SWIFT Member/Sub member
- BEID - Business Entity Identifier
- BROK - Brokers-Dealers
- COOP - Co-operative Agreement with SWIFT
- CSDS - Clearing Houses, Central Depositories
- CUST - Subsidiary Providers of Custodian and Nominee Services
- ETCP - Electronic Trade Confirmation Providers
- EXCH - Recognized Exchanges
- FUAD - Fund Administrators
- IMIS - Investment Management Institutions
- MCFI - Financial Institution in a MA-CUG
- MCCO - Non-Financial Institution Participant in a MA-CUG
- MONE - Money Brokers
- NSFI - Non-Shareholding Financial Institutions
- NSWB - Non SWIFT BIC's
- PRXY - Securities Proxy Voting Agency
- PSPA - Payment System Participants
- REGI - Registrars and Transfer Agents
- SSPA - Securities System Participants
- TESP - Treasury ETC Service Provider
- TRAD - Trading Institutions
- TRAV - Travellers; Cheques Issuers
- TRCO - Treasury Counterparty
- TRUS - Trustees, Fiduciary Service Companies
- ZZZZ - Undefined Institutions

Choose the appropriate one. In case of upload, the system automatically updates this field with the sub-type code corresponding to the BIC.

**BEI Indicator**

The system identifies whether the BEI status for the chosen sub-type code is 'Yes' or 'No' from the back-end maintenance in the 'ISTM\_SUBTYPE\_CODE' table. It checks this option whenever the status in the table for the sub-type code is 'Yes'. You cannot modify this field.

**ADB Member**

Select a value to indicate membership of the specified BIC code in Asian Development Bank (ADB), from the adjoining drop-down list. This list displays the following values:

- Yes – Select if the BIC code holds a membership in ADB.
- No – Select if the BIC code does not hold a membership in ADB.



- Not Applicable – Select if the membership is not applicable for this BIC code.

---

**Note**

- The system maintains 'Not Applicable' as the default value.
  - If 'Not Applicable' is maintained as the status, then the system will not consider the status for validation.
- 

**Payment Message**

You can indicate whether your counterparty whose BIC Code details you are capturing is capacitated to receive payment messages in the MT 103 format. If so, enable the 'Generate MT 103 as Payment Message' option by checking the box.

---

**Note**

However, the Counterparty bank will still receive the payment messages in the MT103 format if you do not enable the box 'Generate MT 103 as Payment Message'

---

If you have chosen the MT 103 option, you can enable the MT 103 + format option if you would like to generate outgoing MT 103 messages in the MT 103 + Format. Enable the MT 103+ option by checking the 'MT 103+ Preferred' box.

You will be allowed to choose the MT 103+ option only if you have enabled the generation of MT 103 messages as Payment Messages. Moreover, you should also ensure that you have also enabled this option:

- For your bank branch in the Branch Parameters Maintenance
- By choosing the Generate 103+ option for currency in the Currency Definition
- For the product used by the contract, in the Product Preferences

The 'other' preferences that you need to specify for each BIC entity are as follows:

- CUG Member – enable this option by checking the box positioned next to this field to indicate that the BIC entity is a Closed User Group member
- Update During Upload
- Black-Listed – this indicates that the BIC entity is also black listed
- Remit Member - This indicates that the customer is registered with MT 103 Extended Remittance Information Multi User Group.

**Multi Customer Credit Transfer**

This option is to indicate whether or not a Multi Credit Transfer Feature [MT102 support] exists between your bank and the BIC entity.

**Maximum Size**

Indicate the maximum size in bytes, agreed upon between the two parties for transmitting a MT102 message. A null value in this field signifies that there is no limit set on the size of the message.

Whenever the queue exceeds the maximum size specified in the BIC maintenance, the system automatically splits the queue into multiple queues to contain the message within the specified limits.

**Generate MT102+**

Check this box to process MT102+ messages. Selecting this check box also required the 'Multi Customer Credit Transfer' checkbox to be selected.

### Generate MT101

This field indicates whether an MT101 can be sent/received from this BIC. Select this option to generate MT101 message.

---

#### Note

This is a primary selection criterion. A separate maintenance for agreements has to be maintained in the function ISDCCYRS to generate the MT101.

---

### No of Transaction per Message

Here you can indicate the no of transactions to be included in an MT101 message. If you do not specify a value it will be defaulted to 10.

---

#### Note

The system generates notification on authorization of any modification, addition or deletion of BIC code.

---

## 2.11.2 Viewing BIC Codes

Oracle FLEXCUBE allows you to store SWIFT BIC in the database. You can directly transfer data from the SWIFT BIC directories to the Oracle FLEXCUBE tables. You can view the uploaded data in the 'BIC Code Summary' screen.

You can invoke the 'BIC Code Summary' screen by typing 'ISSBICDE' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'BIC Code Summary' application window. At the top, there are search options: 'Search', 'Advanced Search', and 'Reset'. Below this, there are several search filters: 'Authorization Status' (dropdown), 'Record Status' (dropdown), 'BIC Code' (text input with a magnifying glass icon), 'Bank Name' (text input with a magnifying glass icon), 'Customer No' (text input with a magnifying glass icon), 'Bank Address 1' (text input with a magnifying glass icon), 'SWIFT Key Arrangement' (dropdown), and 'Relations' (dropdown). Below the filters, there is a pagination control showing 'Records per page: 15' and '1 Of 1' records. A table with 15 rows and 8 columns is displayed. The columns are: Authorization Status, Record Status, BIC Code, Bank Name, Customer No, Bank Address 1, SWIFT Key Arrangement, and Relations. All cells in the table are empty. At the bottom right of the window, there is an 'Exit' button.

The query option is available on the following fields in this screen:

- BIC Code
- National ID (Only BIC Database plus)
- CHIPS UID (Only BIC Database plus)
- Institution name
- Tag (To identify either FI or AM record type)
- City
- Location
- Country Name
- New BIC
- New Branch Code
- Modification

The BIC Code Summary screen operates as an upload table. The data is entered into Oracle FLEXCUBE using these tables.

### 2.11.3 Associating Customer to a BIC Code

You can associate Customer to a BIC Code through 'BIC Code Customer Details' screen. You can invoke this screen by typing 'ISDBICPB' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The 'BIC Code Customer Details' are maintained at 'Customer Maintenance' level. You can specify the following:

#### **BIC Code**

Specify the BIC Code details. Alternatively, you can select the BIC Code from the option list. The list displays all valid values.

#### **Customer Number**

If the bank is a customer of your bank, you can select the CIF ID assigned to the bank from the option list. Once you select the CIF ID, the name of the bank appears in the Customer Name field.

#### **Customer Name**

Specify the Customer Name. Alternatively, you can select the Customer Name from the option list.

---

**Note**

The system displays the name of the specified customer ID based on the details maintained at 'Customer Maintenance' level.

---

**SWIFT Key**

Specify the SWIFT Key details if a SWIFT connectivity exists between your bank and the bank for which you are maintaining details.

**Telex Key**

Specify the Telex Key details if a Telex connectivity exists between your bank and the bank for which you are maintaining details.

**SWIFT Key Arrangement**

Specify whether a SWIFT Key arrangement exists between your bank and the BIC entity. You can select the desired option from the option list:

- Select 'Yes' option if SWIFT Key Arrangement exists
- Select 'No' option if SWIFT Key Arrangement does not exist.

**Relations**

Identify the kind of relationship that exists between your bank and the BIC entity.


Select any one of the following options to indicate the same:

- Select 'No' option to indicate that the BIC Entity is not a customer of your bank.
- Select 'Mail' option if the BIC entity is not a recognized SWIFT entity but an address internal to your bank. In such cases all correspondence directed to the particular BIC entity will be sent as mail messages.
- Select 'Keys' option if a SWIFT /Telex connectivity exists between your bank and the bank for which you are maintaining details. Subsequently, specify the SWIFT/Telex Key in the adjacent field.

#### **2.11.4 Viewing Customer BIC Codes**

Oracle FLEXCUBE allows you to associate customer to BIC codes. You can view the uploaded data in the 'BIC Code Customer Summary' screen.

You can invoke the 'BIC Code Customer Summary' screen by typing 'ISSBICPB' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



The query option is available on the following fields in this screen:

- Authorization Status
- Record Status
- BIC Code
- Customer Number
- Relations

### 2.11.5 Operations on a BIC Record

On an existing BIC code record, you can perform any of the following operations (if a function under the Actions Menu is disabled, it means that the function is not allowed for the record):

Apart from defining a new BIC code record you can perform any of the following operations on an existing record (if any function under the Actions Menu is disabled, it means that the function is not allowed).

- Amend the details of a record
- Authorize a record
- Copy the details of the record
- Close the record
- Reopen the record
- Delete the details of a record

*Refer to the User Manual on Common Procedures for details of these operations.*

It is assumed that the upload source contains details of all relevant BIC codes. The BIC records that are uploaded to Oracle FLEXCUBE should contain the following tags:

- **U** - If records do not exist in the Oracle FLEXCUBE BIC directory, the same would be inserted. For a record that already exists, it will be updated with that of the BIC upload.
- **M** - If there is no existing record in the Oracle FLEXCUBE BIC directory, the same would be inserted. Otherwise the record will be updated with the one in the BIC upload.
- **A** - For an existing record in the Oracle FLEXCUBE BIC directory, an error will be logged and the upload will continue. If no records exist, then a new record will be updated with the one in the BIC upload.

- **D** - If there is no existing record in the Oracle FLEXCUBE BIC directory, an error will be logged and the upload will continue. If there is any record existing, then it will be marked as 'CLOSED'.
- **AM**- For an existing record in the BIC file or AM file, BIC code would be renamed in the upload file

BIC addresses that have changed will be appropriately updated. Addresses bearing the tag D will be automatically deleted. New BIC records will be created for records that bear the tag N.

The network codes that are marked for exclusion in the 'BIC Upload Maintenance' screen will not be uploaded.

The upload sequence is based on the modification tags in the BIC records. The sequence will occur in the following order:

- Deletion
- Modification
- Addition
- Unchanged

The file upload is processed in an asynchronuous manner. The system prompts the user to check the logs.

---

**Note**

The logs can be viewed by visiting Batch Operations -> Intra Day Batch -> Monitor (Fast Path: BASIDMTR). The function field can be given as ISDBICPU% for searching the upload logs

---

Click 'Exit' or 'Cancel' button to exit the screen without initiating the upload process.

### **2.11.6 Maintaining Local Payments Bank Directory**

The local clearing bank codes are maintained using the Local Clearing Bank Code Maintenance which is used for processing the local clearing payments.

This screen also provides the details of the clearing network participation (direct/indirect) for each Scheme defined.

You can invoke the 'Local Payments Bank Directory' screen by typing 'STDBKMNT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

### Branch Code

Select the branch code from the adjoining option list. Alternatively, you can select branch code from the option list. The list displays all valid branch code maintained in the system.

### Branch Name

System defaults the Branch Name on selecting a valid Branch Code.

### Bank Code

Specify the bank code with which the processing bank can interact. This is mapped to IFSC code for India Payments.

### Clearing System Code

Specify the corresponding ISO code or clearing system Code in this field.

### Clearing System Proprietary

Select the corresponding clearing system proprietary.

### Bank Name

Specify the full name of the bank.

### Short Name

Specify a short name to identify the bank.

### Address 1 to 4

Specify the address of the bank.

**City**

Specify the city in which the bank is located.

**Postal Code**

Specify the postal code that forms a part of the address.

**Country**

Select the country code in which the bank is located, from the adjoining option list. All country codes maintained in the system is displayed in this list.

**Main Bank**

Check this box to indicate, that the Bank Code specified is the Main Bank for the Host.

If you check 'Main Bank' check box, then 'Branch Code' and 'Branch Name' should be left blank. The system will allow you to specify the value which is not available in the list

**Main Bank Code**

Select the clearing bank code of the bank which the branch belongs to. If you have specified a branch code, then it is mandatory to select the main bank code.

**SWIFT Address**

Select the SWIFT address of the bank, from the adjoining option list. The list displays all valid swift codes maintained in the system.

**International Bank Account Number Mandatory**

Check this box, if the IBAN of the bank needs to be accompanied with the payment.

**Internal Clearing**

Check this box if the creditor bank is one of the internal banks maintained in the system.

**Clearing Participation****Scheme**

Select the scheme, for which the bank directory details to be maintained. This is a mandatory field. The options in the drop down are:

- SCT
- SDD B2B
- SDD CORE
- SCT INST

The schemes details maintained in Network Maintenance (PMDNWMNT) are listed here.

**Participant Type**

Select the participant type as direct or indirect from the drop down values.

If indirect relationship is selected, then the direct participant bank codes along with the direct bank account number is specified. If a message is received from the indirect participant bank code which is maintained in the local payment bank directory, the system derives the debit account for the payment from the direct bank account number specified for the bank code.

---

**Note**

The networks from PMDNWMNT for which participant type is maintained are listed in the option list for Creditor bank BIC in PADOTONL.

---



**Direct Bank Code**

This field is enabled if participant type is indirect. Select the direct participant bank code from the adjoining option list.

**Addressee**

Specify the participant bank account number in this field. Batch processing is applicable for each payment record for dispatch, if the bank code is enabled for Batch processing.

**Start Date**

Specify the date from which the clearing payments for the specified bank code is valid.

**End Date**

Specify the date till which the clearing payments for the specified bank code is valid.

---

**Note**

Directory details maintained are referred by the following Payments types - ACH, Direct Debit and SEPA Instant. The payment processing is as follows:

- Network is derived, based on the Scheme linked to the Network in PMDNWMNT
  - BIC is validated while processing a payment based on Start date and End Date defined in the Clearing participation grid
  - While validating the BIC, if the derived BIC and scheme combination is not found, BIC is truncated to 8 digits and appended with XXX
-

## 2.11.7 Viewing Local Payments Bank Directory Details

You can view a summary of local payments bank directories maintained through 'Local Payments Bank Directory Summary' screen. To invoke this screen, type 'STSBKMNT' in the field at the top right corner of the application toolbar and click the adjoining arrow button.

Local Payments Bank Directory Summary

Search Advanced Search Reset Clear All

Case Sensitive

Authorization Status  Record Status

Bank Code

Records per page 15 1 Of 1 Go Lock Columns 0

Authorization Status	Record Status	Bank Code	Bank Name	City	Address	Country	SWIFT Address	Internal Clearing	Clearing system Code	Clearing System Proprieta
----------------------	---------------	-----------	-----------	------	---------	---------	---------------	-------------------	----------------------	---------------------------

Exit

You can search for the networks using one or more of the following parameters:

- Authorization status
- Record status
- Bank code

Once you have specified the search parameters, click 'Search' button. The system displays the records that match the search criteria.

Double click a record or select a record and click on 'Details' button to view the detailed network maintenance screen.

## 2.11.8 Maintaining Bank Directory Plus

You can view the details of each BankDirectoryPlus file record in the 'Bank Directory Plus Maintenance' screen. To invoke this screen type 'ISDBKDPL' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

Bank Directory Plus Maintenance

Enter Query

**Unique Details**

Record Key \*

Office Type

Parent Office Key

Head Office Key

Legal Type

Legal Parent Key

**Group Details**

Group Type

Group Parent Key

Institution Status

Cooperative Group Key

ISO LEI Code

**Address Details**

Institution Name

Branch Info

POB Number

Street Address 1

Street Address 2

Street Address 3

Street Address 4

City

CPS

ZIP Code

Country Name

ISO Country Code

Time Zone

**BIC Details**

BIC8

Branch BIC

Exit

### Record Key

Specify the record key.

The system displays the following based on the record key specified:

#### Unique Details

- Office Type
- Parent Office Key
- Head Office Key
- Legal Type
- Legal Parent Key

#### Group Details

- Group Type
- Group Parent Key
- Institution Status
- Cooperative Group Key
- ISO LEI Code

#### Address Details

- Institution Name
- Branch Info

- POB Number
- Street Address 1, 2,3 & 4
- City
- CPS
- ZIP Code
- Country Name
- ISO Country Code
- Time Zone

#### BIC Details

- BIC8
- Branch BIC
- BIC Code
- Chips ID
- National ID
- National ID Type
- Connected BIC

#### Other Details

- Subtype Indicator
- Network Connectivity
- Branch Qualifiers
- Service Codes
- SSI Group Key
- IBAN Key

### **2.11.9 Viewing Bank Directory Plus Details**

You can view the details maintained in the 'Bank Directory Plus Maintenance' screen using the 'Bank Directory Plus Summary' screen. You can invoke this screen by typing 'ISSBKDPL'

in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

LBL\_BANK\_DIRECTORY\_PLUS\_SUMMARY

Search Advanced Search Reset

Record Key \_\_\_\_\_ ρ Office Type \_\_\_\_\_ ρ

Parent Office Key \_\_\_\_\_ ρ Head Office Key \_\_\_\_\_ ρ

Legal Type \_\_\_\_\_ ρ Legal Parent Key \_\_\_\_\_ ρ

Records per page 15 1 Of 1 Go 0

<input type="checkbox"/>	Record Key	Office Type	Parent Office Key	Head Office Key	Legal Type	Legal Parent Key	Group Type	Group Parent Key	Institution Status	Cooperative Group K
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										
<input type="checkbox"/>										

Exit

In the above screen, you can base your queries on any or all of the following parameters and fetch records:

- Record Key
- Parent Office Key
- Legal Type
- Office Type
- Head Office Key
- Legal Parent Key

Select any or all of the above parameters for a query and click 'Search' button. The records meeting the selected criteria are displayed.

- Record Key
- Office Type
- Parent Office Key
- Head Office Key
- Legal Type
- Legal Parent Key
- Group Type
- Group Parent Key
- Institution Status
- Cooperative Group Key
- ISO LEI Code

- BIC8
- Branch BIC
- BIC Code
- Chips ID
- National ID
- Connected BIC
- Institution Name
- Branch Info
- POB Number
- Street Address 1,2. 3 & 4
- City
- CPS
- ZIP Code
- Country Name
- ISO Country Code
- Time Zone
- Subtype Indicator
- Network Connectivity
- Branch Qualifiers
- Service Codes
- SSI Group Key
- IBAN Key

### 2.11.10 Maintaining IBAN Plus

You can view the details of each IBANPlus file record in the 'IBAN Plus Maintenance' screen. To invoke this screen type 'ISDIBNPL' in the field at the top right corner of the Application tool bar and click on the adjoining arrow button.

IBAN Plus Maintenance

Enter Query

**IBAN Details**

<b>Record Key *</b>	_____	IBAN BIC	_____
Institution Name	_____	Routing BIC	_____
Country Name	_____	IBAN National ID	_____
ISO Country Code	_____	Service Context	_____
IBAN ISO Country Code	_____		

Exit

#### **Record Key**

Specify the record key.

The system displays the following based on the record key specified:

- Institution Name
- Country Name
- ISO Country Code
- IBAN ISO Country Code
- IBAN BIC
- Routing BIC
- IBAN National ID
- Service Context

### 2.11.11 Viewing IBAN Plus Details

You can view the details maintained in the 'IBAN Plus Maintenance' screen using the 'IBAN Plus Summary' screen. You can invoke this screen by typing 'ISSIBNPL' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

In the above screen, you can base your queries on any or all of the following parameters and fetch records:

- Record Key
- Country Name
- IBAN ISO Country Code
- Routing BIC
- Institution Name
- ISO Country Code
- IBAN BIC

- IBAN National ID

Select any or all of the above parameters for a query and click 'Search' button. The records meeting the selected criteria are displayed.

- Record Key
- Institution Name
- Country Name
- ISO Country Code
- IBAN ISO Country Code
- IBAN BIC
- Routing BIC
- IBAN National ID
- Service Context

### 2.11.12 Maintaining BICPlusIBAN

Oracle FLEXCUBE supports the Upload of BICPlusIBAN directory.

BICPlusIBAN is a SWIFT directory that lists institution identifiers recognized by the financial industry, for example, Bank Identifier Codes, CHIPS UIDs, national clearing codes, and IBAN-related information. It also provides name and addresses of the corresponding entities.

BICPlusIBAN is used to identify correspondents and counterparties accurately, and to allocate the correct code when sending messages, thus improving Straight Through Processing (STP). Initiators of cross-border payments within Europe are required to submit the BIC and IBAN codes to the receiver in order to benefit from reduced payment transaction charges.

You can invoke the 'BIC and IBAN Summary' screen by typing 'ISSEBANP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



### 2.11.13 Viewing BICPlusIBAN

You can invoke the 'BIC and IBAN Summary' screen by typing 'ISSEBANP' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

#### Unique Key for Record

Specify the unique key of the record in the file. This consists of ISO country code and sequential number of six digits.

### 2.11.14 Maintaining IBAN Information

Invoke the 'IBAN Information Maintenance' screen by typing 'ISDESBAN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Here you can specify the details of the following:

**IBAN Country Code**

Specify the ISO country code prefix in the IBAN.

**IBAN Country Position**

Specify the position of the country code in IBAN.

**IBAN Country Code Length**

Specify the number of characters of the country code in the IBAN.

**IBAN Check Digits Position**

Specify the start position of check digits in the IBAN

**IBAN Check Digits Length**

Enter the Number of check digits in the IBAN

**Bank Identifier Position**

Enter the Start position of bank identifier in the IBAN

**Bank Identifier Length**

Specify the Number of characters of bank identifier in the IBAN

**Branch Identifier Position**

Specify the Start position of the branch identifier in the IBAN (value is empty if the branch identifier is not applied in the country's IBAN format)

**Branch Identifier Length**

Specify the Number of characters of the branch identifier in the IBAN (value is 0 if the branch identifier is not applied in the country's IBAN format)

**IBAN National ID Length**

Specify the Number of significant characters of the National ID value that are used by SWIFT to populate the IBAN NATIONAL ID, and that are sufficient to derive the IBAN BIC correctly.

This number can be different from (that is, smaller than) the length of the national bank/branch identifier defined in the IBAN Registry.

SWIFT refines its IBAN to BIC translation algorithms, this number may change from release to release.

**Account Number Position**

Specify the Start position of the account number in IBAN.

**Account Number Length**

Specify the Number of characters of account number in IBAN

**IBAN Total Length**

Specify the total number of characters of the IBAN.

**Optional Commence Date**

Specify the date from when the IBAN structure is an optional requirement.

**Mandatory Commence Date**

Specify the date from when the IBAN structure is a mandatory requirement.

**SEPA**

Select the SEPA from the adjoining drop-down list. The options are:

Y - Select 'Y' if the IBAN is used in any of the SEPA schemes.

N- Select 'N' if the IBAN is not used in the SEPA schemes.

### 2.11.15 Viewing IBAN Information

Invoke the 'IBAN Information Summary' screen by typing 'ISSESBAN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

IBAN Information Summary

Search Advanced Search Reset

Authorization Status  Record Status

IBAN Country Code

Records per page: 15 1 Of 1 Go 0

<input type="checkbox"/>	Authorization Status	Record Status	IBAN Country Code
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			
<input type="checkbox"/>			

Exit

In the above screen, you can base your queries on any or all of the following parameters and fetch records:

- Authorization Status
- IBAN Country Code
- Record Status

Select any or all of the above parameters for a query and click 'Search' button. The records meeting the selected criteria are displayed.

- Authorization Status
- Record Status
- IBAN Country Code

---

The IBAN Check Digit and IBAN Check National ID validations are applicable only if the IBANPLUS\_REQD global parameter value is 'Y'.

---

## 2.11.16 Uploading BIC Files

SWIFT allows you to upload the entire BIC file or individual records like Amendments (AM) and File Instructions (FI) record files within the BIC upload file, on to the BIC directory. You can perform this through the 'BIC Upload' screen.

The BICPlusIBAN directory consists of the following files:

- BI file (BICPlusIBAN Information)
- IS file (IBAN Structure information)
- The BICPlusIBAN directory should be used to
- Translate beneficiary bank's BIC into national (clearing, sort) code
- Show banks' participation in RTGS system
- Show banks' details (name, address & so on)
- BICPlusIBAN Directory can also be used as an enquiry tool
- SEPA Related:
- Derive BIC from the IBAN, if missing
- Validate IBANs and BICs

On successful upload of BIC Plus IBAN, system populates the SWIFT BIC directory and the clearing codes automatically.

## 2.11.17 IS File Upload

This file forms the part of the BICPlusIBAN package. This contains information about the IBAN structure applicable in the countries. IS File forms are stored in a new data store and are used for IBAN structure validations. Invoke the 'BIC Upload' screen by typing 'ISDBICPU' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

Bank Identifier Code Upload

Save

Source Code \*

File Name \*

File Path \*

Intraday Sequence Number

Submit Parameters Submit Batch

Cancel

Here you can specify the following details:

### **Source Code**

Specify the source from which you want to upload details. You can select the appropriate source code from the drop-down list displaying the following values:

- BIC - Select this to upload the BIC file
- CCH File - Select this to upload the country-wise holiday file
- BIC Plus IBAN - Select this to upload BIC plus IBAN file
- BICPlusIBANIS - Select this to upload IBAN structure file
- BankDirectoryPlus - Select this to upload Bank Directory Plus file
- IBANPlus - Select this to upload IBAN Plus file
- IBANStructure - Select this to upload IBAN structure file
- IBAN EXCLUSION LIST - Select this to upload IBAN exclusion list
- SEPA Plus - Select this to upload SEPA Plus file
- BICPLUS2018 - Select this to upload BIC Plus 2018 file
- BICPLUS2018 Country - Select this to upload BIC Plus 2018 country file
- BICPLUS2018 Currency - Select this to upload BIC Plus 2018 currency file
- BICPLUS2018 Holiday - Select this to upload BIC Plus 2018 holiday file
- BICPLUS2018 Holiday Services - Select this to upload BIC Plus 2018 holiday services file
- BICPLUS2018 TimeZone - Select this to upload BIC Plus 2018 time zone file

#### **File Path**

State the path in the database server where the uploaded file should be stored.

#### **File Name**

Specify a name for the uploaded file. The file name should bear the extension '.DAT'.

#### **Intraday Sequence Number**

The system generates an intraday sequence number when 'Submit Parameters' is clicked.

Click 'Submit Batch' button to start the upload process.

---

#### **Note**

On successful upload of BICPLUS2018 Holiday or BICPLUS2018 Holiday Services, Dates marked as Holiday Type 'H' in upload file will be updated to Holiday in STDCCHOL-Currency Holiday Calendar Maintenance for the corresponding year and currency.

---

### **2.11.18 BIC Record File Formats**

The file formats for the FI and AM records is as under:

**FI record**

<b>Position</b>	<b>Description</b>	<b>Length</b>	<b>Type</b>	<b>Mandatory</b>	<b>Data</b>
1	Tag Identifier	2	VAR-CHAR2	Y	'FI'
3	Modification Flag	1	VAR-CHAR2	Y	'A' addition 'M' modification 'D' deletion 'U' unchanged
4	BIC (Bank, Country & Location Code)	8	VAR-CHAR2	Y	Bank code (4 char) Country code (2 char) Location code (2 char)
12	BIC (Branch code)	3	VAR-CHAR2	Y	Branch code, with - 'XXX' if no branch code exists
15	Institution Name	35	VAR-CHAR2	Y	Name (first part)
50	Institution Name	35	VAR-CHAR2	N	Name (second part)
85	Institution Name	35	VAR-CHAR2	N	Name (third part)
120	Branch Information	35	VAR-CHAR2	N	Branch specification (first part)
155	Branch Information	35	VAR-CHAR2	N	Branch specification (second part)
190	City Heading	35	VAR-CHAR2	Y	City name
225	Subtype indication	4	VAR-CHAR2	Y	A subtype can be bank, broker, etc.

229	Value Added Services	60	VAR-CHAR2	N	20 x 3 char. Fields indicating the Value-added Service Code
289	Extra Information	35	VAR-CHAR2	N	Specific information
324	Physical address	35	VAR-CHAR2	N	Physical address (first part)
359	Physical address	35	VAR-CHAR2	N	Physical address (second part)
394	Physical address	35	VAR-CHAR2	N	Physical address (third part)
429	Physical address	35	VAR-CHAR2	N	Physical address (fourth part)
464	Location	35	VAR-CHAR2	N	Location (first part)
199	Location	35	VAR-CHAR2	N	Location (second part)
534	Location	35	VAR-CHAR2	N	Location (third part)
569	Country name	35	VAR-CHAR2	N	Country name (first part)
604	Country name	35	VAR-CHAR2	N	Country name (second part)
639	POB Number	35	VAR-CHAR2	N	Post Office Box number
674	POB Location	35	VAR-CHAR2	N	POB Location (first part)
709	POB Location	35	VAR-CHAR2	N	POB Location (second part)
744	POB Location	35	VAR-CHAR2	N	POB Location (third part)
779	POB Country name	35	VAR-CHAR2	N	POB Country name (first part)
814	POB Country name	35	VAR-CHAR2	N	POB Country name (second part)

## AM record

The AM record would consist of only the tag identifier, old BIC and the new BIC. The file format is as follows:

Position	Description	Length	Type	Mandatory	Data
1	Tag Identifier	2	VAR-CHAR2	Y	'AM'
3	Old BIC	11	VAR-CHAR2	Y	Old BIC
14	New BIC	11	VAR-CHAR2	Y	New BIC

### 2.11.19 Local Bank Directory View

You can invoke the 'Local Bank Directory View' screen by typing 'ISDBKDIR' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can specify the following details:

#### Network Directory Key

This field displays the Network Directory Key. The participant banks for different Networks are differentiated using the Network Directory Key.

Directory in OBPM	Directory Keys Applicable
RTGS Directory	TARGET2 EURO1 LVTS



Directory in OBPM	Directory Keys Applicable
Local Payment Bank Directory	SCT SDD B2B SDD CORE SCT INST
ACH Directory	Directory keys as defined in OBPM

**Bank Code**

Clearing Member ID of the participant banks in the Clearing Network is populated in this field.

**Bank Name**

Clearing participant Bank Name is displayed in this field.

**Clearing system Code**

If the Clearing System Code is part of ISO published list of codes in External code list for External Clearing System Identification<sup>1</sup>, it is populated in Clearing System Code field.

**Clearing System Proprietary**

If the Clearing code is a proprietary code it will be populated in Clearing System Proprietary field.

---

**Note**

Only one of the fields Network Clearing Code / Proprietary Clearing Code can have a value.

---

**Network Participation**

This field displays the Network Participation.

**Direct Bank Code**

The Direct Bank Code is applicable if the bank is an indirect participant in the Clearing Network. Direct Bank Code is a valid Bank Code with the same Network Directory Key and Participant type 'Direct'.

**Valid From Date**

This field displays the valid from date for the record.

**Valid Till Date**

This field displays the valid till date for the record.

This screen displays below fields also:

- BIC Details
- Unstructured Address Details
- Structured Address Details
- Address Type

## 2.11.19.1 Local Bank Directory View Summary

You can invoke “Local Bank Directory View Summary” screen by typing ‘ISSBKDIR’ in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Local Bank Directory View Summary

Search Advanced Search Reset Clear All

Case Sensitive

Bank Code \_\_\_\_\_ Record Status \_\_\_\_\_ Clearing system Code \_\_\_\_\_  
Network Directory Key \_\_\_\_\_ Bank Name \_\_\_\_\_ Clearing System Proprietary \_\_\_\_\_

Records per page: 15 1 Of 1 Lock Columns: 0

Bank Code	Record Status	Clearing system Code	Network Directory Key	Bank Name	Clearing System Proprietary	Network Participation	Direct Bank Code	Valid From Date	Valid Till Date	BIC
-----------	---------------	----------------------	-----------------------	-----------	-----------------------------	-----------------------	------------------	-----------------	-----------------	-----

Exit

You can search using the following parameter:

- Bank Code
- Network Directory Key
- Record Status
- Bank Name
- Clearing system Code
- Clearing System Proprietary

Once you have specified the search parameters, click ‘Search’ button. The system displays the records that match the search criteria.

## 2.12 MIS Details Maintenance

This section contains the following topics:

- [Section 2.12.1, "Maintaining MIS Class"](#)
- [Section 2.12.2, "Saving the Record"](#)
- [Section 2.12.3, "Maintaining MIS Group"](#)
- [Section 2.12.4, "Operations on the MIS Group Record"](#)
- [Section 2.12.5, "Maintaining MIS Cost Codes"](#)
- [Section 2.12.6, "Operations on the MIS Cost Code Record"](#)
- [Section 2.12.7, "Maintaining MIS Pool"](#)

### 2.12.1 Maintaining MIS Class

In order to maintain MIS classes, you need to invoke the ‘MIS Class Maintenance’ screen by typing ‘GLDCLSMT’ in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button. In this screen, you can define various categories based on

which reports on general ledgers should be classified. To maintain details of a new MIS class, click new icon.

Here you can maintain the following details:

### MIS class

In Oracle FLEXCUBE, each MIS class that you maintain is identified by a unique nine-character code called a Class Code. You can follow your own convention for devising this code.

### Description

You can specify a short description that will enable you to identify the MIS class quickly. The short description that you specify is for information purposes only and will not be printed on any customer correspondence.

### MIS Type

An important detail in defining an MIS class is to specify the *type* of class that you are creating. The MIS class type identifies the basic nature of the class. In Oracle FLEXCUBE you can set up the following type of MIS classes:

- *Transaction class* — A transaction class refers to all transactions that have taken place through any of the front-end modules like foreign exchange, money market etc. Customer Class relates to customer accounts.
- *Customer class* — Select this option if you are defining a customer-based classification.
- *Composite class* — Choose this option to indicate that the MIS class can be used both at customer definition and at the time of processing a transaction.
- *Fund class* — Refer to the Core Services User manual for details on setting up a Fund MIS class

This is the basic feature of a class and will determine the type of MIS codes that can constitute the class. For each of these MIS types you can create a maximum of ten classes.

**Mandatory**

Using this field, you can indicate whether entering an MIS code is mandatory for a particular MIS class or not. Whenever any transaction is stored, the system checks if an MIS code is supplied for this MIS class invoked in the transaction.

**MIS Codes**

Under a class, you can indicate the sub-divisions that should be reported under the class. Each of the sub-classes is given unique code identifiers.

The MIS codes that you associate with a class will fall under the class at the time of reporting or consolidation.

Click add icon to associate an MIS code to a class. To remove an MIS class from the list, place your cursor in that row and click delete icon.

The MIS codes that you associate will depend on the Type of MIS Class that you are creating. While setting up the details of a customer, you can associate the customer to a customer type MIS Code. Therefore the set up serves more for management purposes and makes the management of GLs simple and easy.

**2.12.2 Saving the Record**

Click save icon to save the record. Click delete icon to exit without saving the details that you entered. An MIS Class that you have created will be available for use only after it has been authorized by a user bearing another ID.

Similarly, you cannot make any modifications to a Class or Category until the previous modification made, has been authorized. After you have made the required entries, click 'Exit' button to exit the screen. You will be returned to the Application Browser.

### 2.12.3 Maintaining MIS Group

You can invoke the 'MIS Group Maintenance' screen by typing 'MIDGRPMT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows the 'MIS Group Maintenance' application window. The window title is 'MIS Group Maintenance'. The interface includes a 'New' icon in the top left corner. The main area contains several input fields: 'MIS Group \*', 'Group Description', 'Pool Code', and 'Description'. Below these fields are four tabs: 'Customer Class', 'Composite Class', 'Transaction Class', and 'Cost Code'. The 'Customer Class' tab is selected, displaying a list of ten MIS Classes (MIS Class 1 through MIS Class 10). Each class has a 'MIS Code' input field and a 'MIS Code Description' field. At the bottom of the window, there is a 'Fields' section with 'Input By Date Time', 'Authorized By Date Time', and 'Modification Number' (with 'Authorized' and 'Open' checkboxes). An 'Exit' button is located in the bottom right corner.

If you are creating a new MIS Group, select 'New' from the Actions Menu in the Application toolbar or click new icon. The 'MIS Group Definition' screen is displayed without any details.

If you are calling an MIS Group that has already been defined, double-click an MIS Group from the summary screen.

### 2.12.4 Operations on the MIS Group Record

On an existing MIS Group record, you can perform any of the following operations (if any function under the Actions Menu is disabled, it means that the function is not allowed for the record):

- Amend the details of an MIS Group
- Authorize an MIS Group
- Copy the details an MIS Group on to a new one
- Print the details of an MIS Group
- Delete an MIS Group

Please refer to the manual on Procedures for details of these operations.

### 2.12.5 Maintaining MIS Cost Codes

An MIS cost code represents the notional cost incurred for a transaction. An MIS cost code can be attached either to an account or to a contract, in the following manner:

3. You can link a Cost Code to an account class. This will default to the accounts maintained under the account class. You can change this default. Alternatively, you can link an MIS Cost Code to an account when maintaining it.
4. When creating a product, you can identify the Cost Codes against which contracts involving the product should be reported.
5. When processing a contract, the Cost Codes identified for the product (the contract involves) will automatically default. These defaults can be changed. If cost codes have not been identified for the product, you can identify one for the contract.

The notional cost will be reported in the profitability report.

You can invoke this screen by typing 'MIDXCODE' in the field at the top right corner of the Application toolbar and clicking the adjoining arrow button.

The screenshot shows the 'MIS Cost Code Maintenance' application window. The window title is 'MIS Cost Code Maintenance'. Below the title bar is a 'New' button. The main area contains a form with the following fields: 'Cost Code \*' (text input), 'Description \*' (text input), 'Type \*' (dropdown menu), 'Currency \*' (text input), 'Amount \*' (text input), 'Periodicity' (dropdown menu), and 'Applied Month' (dropdown menu). At the bottom, there is a 'Fields' section with a table of fields: 'Maker', 'Date Time:', 'Mod No', 'Record Status', 'Checker', 'Date Time:', 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

If you are creating a new MIS Cost Code, select 'New' from the Actions Menu in the Application toolbar or click new icon. The 'MIS Cost Code Maintenance' screen is displayed without any details.

If you are calling an MIS Cost Code that has already been defined, double-click on an MIS Cost Code from the summary screen.

## **Type**

The MIS Cost Code can belong to one of the following types:

### **Number of Transactions**

This typically applies for calculating the cost of processing a transaction involving an account.

You can indicate the amount to be considered as the notional cost for each transaction.

For example, you may incur a certain amount for every transaction you process of a savings account a particular category. This cost could be different for processing transactions in a different type of savings account or for current accounts. You should define different MIS Cost Codes and link them to the appropriate account classes.

### **Event based Charges**

The notional cost applicable for processing an event can be defined as a cost code. Typically, this applies for a contract.

For example, for processing an event in the life-cycle of a loan, you may want to attach a certain cost. You can define a cost code for it and link it to the product.

Similarly, you can define a different notional cost for different events in the life-cycle of a contract. Thus, you can have a cost code for initiating a loan, one for liquidating interest, and so on, and link them to the product with the appropriate event codes.

The notional cost that you define will be taken as the cost per event.

### **Duration based charges**

These charges are applied typically for a contract. The notional cost in this case, is calculated on the basis of a specific duration. This notional cost is defined for a cost code. The following example illustrates how this cost is applied on a contract.

For example, if a loan is live for a month, the notional cost you incur is a specific amount. You would define a duration based cost code, define the periodicity as 'monthly'. For every month a loan linked to the cost code is live, the notional cost will be applied.

## **Cost**

The notional cost, along with the currency in which it is expressed should be indicated for the cost code. The cost will be applied based on the Cost Code type, as follows:

<b>Cost Code Type</b>	<b>Description</b>
Number of Transactions	The amount is taken as the cost per transaction
Event	The amount is taken as the cost per event
Duration	The amount is taken as the cost for the period defined as the periodicity, for the cost code

If a currency conversion is involved during reporting, the prevailing conversion rate will be used.

## **Periodicity**

This is the periodicity at which the costs defined have to be applied. In the profitability report, the notional cost reported would depend on the periodicity defined for the cost code.

For a quarterly, half-yearly or yearly periodicity, you should also indicate the first month of application. The subsequent application months would be computed based on this.

### **2.12.6 Operations on the MIS Cost Code Record**

On an existing MIS Cost Code record, you can perform any of the following operations (if any function under the Actions Menu is disabled, it means that the function is not allowed for the record):

- Amend the details of an MIS Cost Code
- Authorize an MIS Cost Code
- Copy the details an MIS Cost Code on to a new one
- Print the details of an MIS Cost Code
- Delete an MIS Cost Code

Please refer to the manual on Common Procedures for details of these operations.

### **2.12.7 Maintaining MIS Pool**

You can invoke the 'MIS Pool Code Maintenance' screen by typing 'MIDXPOLD' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows a software window titled "Pool Maintenance" with a "New" tab selected. The form contains three required fields: "Pool Code\*", "Pool Name\*", and "Calculation Method\*" (a dropdown menu). Below the form is a "Fields" section with a table structure:

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:		Authorization Status

An "Exit" button is located in the bottom right corner of the window.

If you are creating a new MIS Pool Code, select 'New' from the Actions Menu in the Application toolbar or click new icon. The 'MIS Pool Code Definition' screen is displayed without any details.

If you are calling an MIS Pool Code that has already been defined, double-click on an MIS Pool Code from the summary screen.



## 2.13 User Defined Fields Maintenance

This section contains the following topics:

- [Section 2.13.1, "Invoking the User Defined Fields Maintenance Screen"](#)
- [Section 2.13.2, "Mapping UDF Function Field"](#)

### 2.13.1 Invoking the User Defined Fields Maintenance Screen

Based on your requirement and the nature of the field, you can specify default values and validations for the field. Oracle FLEXCUBE will validate all entries made to the field against the validations you define for a field. You can invoke the 'User Defined Fields Maintenance' screen by typing 'UDDUDFMT' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

The screenshot shows the 'User Defined Fields Maintenance' application window. The main content area is titled 'New' and is divided into several sections for defining a field:

- Field:** Includes 'Field Name \*', 'Field Description \*', and 'Field Type \*' (dropdown). On the right, there are 'Usage Allowed \*' (dropdown), 'Function' (text input), and 'Validation Type \*' (dropdown).
- Length:** Features a checkbox for 'Fixed Length'. Below it are 'Fixed Length' (text input), 'Minimum Length' (text input), and 'Maximum Length' (text input).
- Range:** Includes 'Minimum Value' (text input), 'Maximum Value' (text input), 'Mask' (text input), and 'Default Value' (text input).
- Flags:** Contains three checkboxes: 'Amendable', 'Unique Field', and 'Update Allowed'.

At the bottom of the window, there is a navigation bar with tabs for 'LOV', 'Derivation', 'Validation', and 'Cube Entity'. Below the navigation bar is a summary table with the following columns: 'Maker', 'Checker', 'Date Time:', 'Mod No', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner of the window.

A field that you have created will become operational in Oracle FLEXCUBE only after it is authorized. A user bearing a different Login ID can authorize a field definition record that you have created.

## 2.13.2 Mapping UDF Function Field

You can maintain the user defined fields function mapping in the User Defined Fields Function Field Mapping Maintenance screen. To invoke this screen type 'UDDFFLMT' in the top right corner of the application toolbar and click the adjoining arrow button.

The screenshot shows a software interface for maintaining function field mappings. The main area is a table with one column labeled 'Field Name'. Above the table, there is a 'Function \*' field and a 'Field Details' section with navigation controls. The bottom of the screen contains a status bar with fields for 'Maker', 'Checker', 'Date Time', 'Mod No', 'Record Status', and 'Authorization Status', and an 'Exit' button.

You can specify the following in this screen:

### Function

Specify the function ID. Alternatively, you can select the function from the option list. The list displays all valid functions maintained in the system.

### Field Name

Specify the name of the field. Alternatively, you can select the field name from the option list. The list displays all valid fields maintained in the system.

## 2.14 Generic Interface Maintenance

This section contains the following topics:

- [Section 2.14.1, "Invoking GI Process"](#)
- [Section 2.14.2, "Viewing Error Details of Individual Record"](#)
- [Section 2.14.3, "Specifying Interface Definition Details"](#)
- [Section 2.14.4, "Viewing Interface Definition Summary"](#)
- [Section 2.14.5, "Maintaining AUDF \(ASCII User Defined Function\) Details"](#)
- [Section 2.14.6, "Viewing AUDF Summary Details"](#)

### 2.14.0.1 Maintaining GI Parameter

You can set the parameters for the framework of Generic Interface processing in the following screen 'Parameters' screen invoked from the Application Browser. You can invoke this screen

by typing 'GIDPARAM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can maintain the following parameters for generic interface here.

### **Holiday Treatment**

You can specify the parameters for interface processing if the schedule date falls on a holiday.

#### **Holiday Treatment**

Check this box to indicate your preference for interface processing on a holiday.

#### **Next Run Date**

Specify how the system should process if the schedule date falls on a holiday. You can select the options as either move the interface processing to previous working date or next working date if the interface processing date falls on a holiday.

---

#### **Note**

The default holiday treatment is movement to 'next working date'.

---

### **Purging Days**

Specify the purging days if you want to maintain any days to be purged while processing interface.

### **Incoming**

You can specify the parameters for interface processing for the incoming files.

#### **Uploaded Record Status**

Select the input status of the transaction record after upload as:

- Authorized
- Unauthorized

---

**Note**

By default 'Authorized' option is selected.

---

**Bad File Path**

Specify the path where the external tables should write the bad records, while reading from the Incoming file.

**Log file Path**

Specify the path where the external tables should write the Log file, while reading from the Incoming file.

**Outgoing**

You can specify the parameters for interface processing for the outgoing files.

**Archival Required**

Check this box to specify if the upload table data and file log data should be archived at the time of EOD or before deleting the same.

**File writing process**

Select the tool to write the data into output file from the following options:

- Oracle - This component uses ORACLE UTIL packages to write the data into output file.
- Java - This component uses java libraries ages to write the data into output file

---

**Note**

By default 'Oracle' option is selected.

---

You need to note the following details while selecting the tool for file writing:

- This feature is applicable only for the outgoing process
- Low volume sites are recommended to use Oracle tool only in case of high volume Java tool is recommended.
- If Java tool is selected then the necessary Java software/component should be installed in the database server and jvm is enabled in database.

## 2.14.1 Invoking GI Process

You can trigger the process of Generic Interface using Gateway Messages, EOD run or through 'Interface Trigger' screen. You can invoke this screen by typing 'GIDIFPRS' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Interface Trigger' application window. The window title is 'Interface Trigger'. The main area contains a form with the following fields: 'Branch Code \* 000' (text input), 'Interface Code \*' (text input with a dropdown arrow), 'External System \*' (text input), 'Interface' (text input), 'File Name' (text input with a dropdown arrow), 'Status' (text input with 'U'), 'Process Code' (dropdown menu with 'File Processing'), 'Physical File Name' (text input), and 'File Mask' (text input). There is a 'File upload' button next to the 'File Name' field. At the bottom, there is a 'Process' button. The footer area contains 'Input By Date Time', 'Authorized By Date Time', 'Modification Number', 'Authorized' (checkbox), 'Open' (checkbox), and an 'Exit' button.

You can provide the following details here to invoke the GI routing package.

### Branch Code

Specify the branch code from where the GI file process has to be initiated.

### Interface Code

Select the Interface Code that has to be processed.

Based on the selected interface code, system defaults external system and interface type.

### File Name

Specify the file name if the selected Interface Code is Incoming.

### Process Code

Select the process code from the drop-down list, if the selected Interface Code is Incoming. The options available are:

- FP – Populating the Upload tables using the file data.
- DP – Populating the Base tables from the Upload tables.
- AL – This will trigger 'FP' and 'DP' processes one after another.
- RT – This is Retry operation the previous process that failed is triggered.
- RE – This will rerun the 'DP' process for error records.

### Physical File Name

A physical file name is applicable if you are processing a file that is uploaded through the 'Interface Trigger' screen.

When the file upload is successful, the system will display the name of the file in this field.

## File Mask

The system displays the incoming file mask specified during interface definition.

### 2.14.2 Viewing Error Details of Individual Record

You can view the individual record error details of the uploaded file in the 'View Error Details' (GIDFILOG) screen. From the summary screen (GISFILOG), double click the selected record to view the error details screen.

You can invoke View Error Details screen by typing 'GIDFILOG' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

File log Detailed

Enter Query

Upload File Name \_\_\_\_\_

Branch Code \_\_\_\_\_

Interface Code \_\_\_\_\_

Process Reference Number \_\_\_\_\_

File Name \_\_\_\_\_

Start Date Stamp \_\_\_\_\_

End Date Stamp \_\_\_\_\_

Status \_\_\_\_\_

Field Mapping Details

Key 1 \_\_\_\_\_

Key 2 \_\_\_\_\_

Key 3 \_\_\_\_\_

Key 4 \_\_\_\_\_

Key 5 \_\_\_\_\_

1 Of 1

Go

Key 1	Key 2	Key 3	Key 4	Key 5
-------	-------	-------	-------	-------

Exit

Based on the upload file name and process reference number, system displays the error details here:

- Upload File Name
- Branch code
- Interface Code
- Process Reference Number
- File Name
- Started Time
- Ended Time
- Status

Following field mapping details are also displayed

- Key 1
- Key 2
- Key 3
- Key 4
- Key 5
- Error Code

- Error Description

### 2.14.3 Specifying Interface Definition Details

You can define the format details and properties associated with interface file in the 'Interface Definition' screen. You can invoke this screen by typing 'GIDIFTDF' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can define the following interface file properties, formats and components here.

#### Branch Code

Specify the code of the branch to which the interface belongs.

#### Interface Code

Specify a unique interface code to identify the interface as incoming or outgoing.

#### Interface Type

Select the interface type from the following options:

- Incoming - Select this option if the file data needs to be uploaded into Oracle FLEXCUBE
- Outgoing - Select this option if data from Oracle FLEXCUBE needs to be written into file

#### External System

Specify the external system with which Oracle FLEXCUBE is interfacing.

#### File Directory

Specify the Oracle directory name. All the incoming/outgoing files will be copied to the path specified for this Oracle directory name. The name of the Oracle directory specified here should correspond to the path ending with 'ready' folder.

Data Controller (Bank) can use the OS features to manage and control access to the data files.

**File Mask**

Specify the file mask for the outgoing interface file.

**2.14.3.1 Main Tab****Frequency Details****Frequency Type**

Select the frequency type for interface file processing from the following drop-down options:

- Daily
- Weekly
- Fort Nightly
- Monthly
- Quarterly
- Half-yearly
- Yearly
- Adhoc

---

**Note**

If Adhoc is specified it will override any existing restrictions.

---

**Week Day**

If you select frequency type as 'Weekly', select the day from the drop-down list for processing the interface file. The options available are:

- Sunday
- Monday
- Tuesday
- Wednesday
- Thursday
- Friday
- Saturday

**Month**

If you select frequency type as 'Quarterly, Half Yearly and Yearly', select the month for the interface file execution from the drop-down list. The options available are:

- January
- February
- March
- April
- May
- June
- July
- August
- September
- October
- November



- December

**Date**

If you select frequency type as 'Monthly, Quarterly, Half Yearly and Yearly', select the date of the month for the interface file execution from the drop-down list.

**Pre Message AUDF**

Specify the AUDF that needs to be invoked before triggering the interface. You can use this to add additional functionality required at the message level.

**Post Message AUDF**

Specify the AUDF that needs to be invoked after triggering the interface. You can use this to add additional functionality required at the message level.

**Incoming**

You can specify the interface details applicable for incoming file details here.

**Function ID**

Specify the function id for which the incoming data need to be sent.

**Processed File Mask**

Specify the file mask for renaming the incoming file after uploading the data.

**Default Action**

Select the default action which needs to be invoked to process the uploaded data in the upload table from the drop-down list below:

- New
- Modify
- Close

**On Override**

Select the action to be taken if an override occurs from the drop-down list below:

- Reject
- Continue
- Skip

**Suppress Start Reference**

Check this box to indicate that the start reference number should be suppressed.

If the checkbox is selected and start reference element is defined in the component definition, system raises an error message while saving the interface. System validates the start reference check for Header, Body and Footer.

For a given interface, mask and suppress start reference are applicable to all the file names configured for that interface

**Incoming File Mask**

Specify the file mask for selecting the incoming files from the file directory. System supports four types of file masking:

- Date and Time mask (YYYYMMDDHHMISS) – (year, month, date, hours, minutes and second)
- Sequence number based mask(nnn) – 3 digit numeric numbers

- File names starting with a specific signature. (Upload all files which are starting with incoming File name)
- Exact File Name (File Names which are exact match with the file name in interface definition)

System searches all the files which are matching the mask criteria and process the files one by one “\_” as the split separator for the file name and the mask criteria.

---

**Note**

System will continue or break the uploading of records based on the error handling defined in the 'On Override' field. If it is Continue, then the system will ignore the current record and continue with the next record. If it is Reject, then the system will stop the execution of the file and start executing the next available incoming file.

---

---

**Note**

By default system append the Incoming File Mask type to the file name while searching the physical file name. If an interface supports for multiple type incoming files, then same file mask is applicable for all type of incoming files.

---

**Outgoing Interface**

Specify the corresponding outgoing interface file for the above incoming file.

**Log Output**

Select the type of details to be updated in the log file from the adjoining drop-down list. This list displays the following values:

- Error
- Success
- Both

While processing the interface file, system verifies the log output value and the below details:

- If the value of “Log Output” is “Error”, then, system creates an error file (<INTERFACE\_NAME>\_FILENAME>\_ERR\_<ProcessRefNo>.dat) in Log\_Failure folder and update the primary key elements and the corresponding error details (error code and message).
- If the value of “Log Output” is “Success”, then, system creates a data file (<INTERFACE\_NAME>\_FILENAME>\_SUC\_<ProcessRefNo>.dat) in Log\_Success folder and update the primary key elements. “
- If the value of “Log Output” is “Both”, then, system creates both error file and data file in log folder.

During the interface configuration, log\_failure and log\_success folders are created in the interface configured folder.

**Last Run Date**

The last run date gets displayed here.

**Next Run Date**

The day on which the interface can be triggered gets displayed here.

## 2.14.3.2 Format Details Tab

You can define the format details in the 'Interface Definition' screen. Click the Format Details tab in the 'Interface Definition' screen and specify the fields.

Interface Definition

Save

Branch Code \* 000

Interface Code \*

Interface Type Incoming

External System \*

File Directory \*

Filemask

Main **Format Details** Preferences

**Data Alignment**

Date

Number

Text

**Format Type**

Format Type Fixed

Delimiting Character

Optional Enclosed Field

Date Format \* YYYYMMDD

**Padding Character**

Date

Number

Text

**Schedule Details**

Schedule

**Start Time**

Hour 0

Min 0

**End Time**

Hour 23

Min 59

Component Details | Incoming File Names

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:		Authorization Status

Cancel

### Data Alignment

#### **Date**

Select the justification type for date field from the drop-down list. The options are:

- Right
- Left

#### **Number**

Select the justification type for number field from the drop-down list. The options are:

- Right
- Left

#### **Text**

Select the justification type for text field from the drop-down list. The options are:

- Right
- Left

---

#### **Note**

Default justification type for text and date field type is Left and number field type is right.

---

## **Padding Character**

You can specify the padding character of fixed length format type interface file here. All the data types can have the same padding character

### **Date**

Specify the padding character for date field.

### **Number**

Specify the padding character for number field..

### **Text**

Specify the padding character for text field.

---

### **Note**

All the data types can have the same padding character.

---

## **Format Type**

### **Format Type**

Select the type of data length in the interface from the following options:

- Fixed – Select this option if the file data has to be in fixed width.
- Delimited - Select this option if the file data has to be in delimited format.

Delimiting Character field gets enabled for you to specify the delimiting character if you select the format type of definition as 'Delimited'.

### **Delimiting Character**

Specify the delimiting character if you select the format type of definition as 'Delimited'.

### **Date Format**

Specify the date format for the interface file.

### 2.14.3.3 Preferences Tab

Click the Preferences tab in the 'Interface Definition' screen and specify the fields.

The screenshot shows the 'Interface Definition' window with the 'Preferences' tab selected. The window is titled 'Interface Definition' and has a 'Save' button at the top left. The 'Preferences' tab is active, showing various configuration options. The 'Branch Code' is set to '000'. The 'Interface Code' is empty. The 'Interface Type' is set to 'Incoming'. The 'External System' is empty. The 'File Directory' is empty. The 'Filemask' is empty. The 'CRC Required' checkbox is unchecked. The 'CRC Algorithm' is empty. The 'CRC File Mask' is empty. The 'CRC File Directory' is empty. The 'Confirmation File Required' checkbox is unchecked. The 'Confirmation File Mask' is empty. The 'Confirmation File Directory' is empty. The 'Character Set' is empty. The 'Parallel Process Required' checkbox is unchecked. The 'Parallel Process' is empty. The 'No Of Records' is empty. The 'No Of Parallel Process' is empty. The 'Data Log Required' checkbox is unchecked. The 'Custom Logging' checkbox is unchecked. The 'When To Run' dropdown is set to 'Manual'. The 'Mandatory' checkbox is unchecked. The 'Trigger Type' dropdown is set to 'Manual'. The 'No Of Executions/Day' is empty. The 'Commit/Fetch Frequency' is set to '500'. The 'Duplication File Check Required For Current Date' checkbox is unchecked. The 'Backward Compatibility' dropdown is set to 'No'. A 'Cancel' button is located at the bottom right of the window.

#### Preferences

##### CRC Required

Check this box if you want to check the CRC while transferring the data.

In case of incoming interface, system checks for the CRC value in the file name maintained in 'CRC file mask'. For outgoing interface, system generates the CRC value in a CRC file.

##### CRC Algorithm

Specify the CRC algorithm which has to be used to calculate the CRC Value.

##### CRC File Mask

The path of CRC File mask gets displayed here.

##### CRC File Directory

The directory of CRC file gets displayed here. However you can modify it. If the file directory is modified, the path for this directory should end with 'ready' folder.

##### Confirmation File Required

Check this box to indicate if confirmation is required for an incoming file. If this box is checked then when incoming file is processed, system checks whether confirmation file is available in the folder specified. If the file is not available then incoming file processes will raise an error indicating the confirmation file is not available.

##### Confirmation File Mask

The path of confirmation file mask gets displayed here.

##### Confirmation File Directory

The directory of confirmation file gets displayed here. However, you can modify it. If the file directory is modified, the path for this directory should end with 'ready' folder.

##### Character Set

Specify the Character Set from the displayed list of character set values.

### **Data Log Required**

Check this box to indicate if the confirmation details are required in the log file.

### **When to Run**

Select the stage of application the interface has to be triggered.

### **Mandatory**

Check this box to indicate that the interface has to be mandatorily processed before moving on to the next stage of EOD. If this box is checked system checks if the interface has been processed or not and if it is not processed system will not allow movement to the next EOD stage.

### **Trigger Type**

Select an appropriate option to indicate how the interface should be triggered. The options available are:

- Manual – Select this option if the interface has to be triggered manually.
- System – Select this option if the interface has to be triggered automatically.

During EOD if there are any mandatory unprocessed interfaces and if the triggering type is selected as 'System' then the interface is triggered automatically. In case of Incoming interface if triggering type is selected as 'System' then system checks if the file is available in the 'ready' folder for that interface. If the file is present the system will process it. In case of outgoing interface if triggering type is selected as 'System' then, system will automatically trigger the Outgoing interface.

---

#### **Note**

If the interface is mandatory, the triggering type must be system. Even if the triggering type is mentioned as System, you can manually trigger the interface whenever required through Interface triggering screen.

---

### **No of Executions/Day**

If you select frequency type as 'Daily', specify the total number of interface file processing executions in a day.

This field is applicable only for incoming interface file process.

### **Commit/Fetch Frequency**

Specify the number of transaction committed or fetched at a given point of time.

### **Duplication File Check Required for Current Date**

Check this box to indicate that the duplicate files should not be added for the current date.

### **Backward Compatibility**

Select the Backward Compatibility value from the drop-down list to indicate the dynamic package generation behavior for an incoming interface. The available options are:

- No - For Online and extensible screen, the Backward Compatibility value is **No**. The user can change the value to **Yes** if required.
- Yes - For Online and non-extensible screen, the Backward Compatibility value is **Yes**.
- Not Applicable - For all non-online screen, the Backward Compatibility value is **Not Applicable**.

## **Parallel Process**

You can specify the parallel process details here.

### **Parallel Process Required**

Check this box to indicate if parallel processing is required if multiple interface files has to be processed at a given time.

When you select parallel process required parallel process type field gets enabled.

### **Parallel Process**

Select the type of parallel process you want to keep for the interface processing:

- Record Based – Select this option if you want parallel processing to be based on the number of records you maintained.
- Process Based – Select this option if you want parallel processing to be based on the number of parallel processes that you maintained.

### **No of Records**

Specify the number of records of parallel process can be performed at a given time. This field gets enabled only if you select the parallel process type as 'Record based'.

### **No of Parallel Process**

Specify the number of parallel process can be performed at a given time. This field gets enabled only if you select the parallel process type as 'Process based'.

## **2.14.4 Viewing Interface Definition Summary**

You can view the interface details maintained in the system using 'Interface Definition Summary' screen. You can invoke this screen by typing 'GISIFTDF' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a web application window titled 'GISIFTDF\_ Desc'. At the top, there are search options: 'Search', 'Advanced Search', 'Reset', and 'Clear All'. Below this is a 'Case Sensitive' checkbox. The search filters are arranged in two columns: 'Authorization Status' (dropdown), 'Record Status' (dropdown), 'Branch Code' (text input with a magnifying glass icon), 'External System' (text input with a magnifying glass icon), 'Interface Code' (text input with a magnifying glass icon), and 'Interface Type' (dropdown). Below the filters is a pagination bar showing 'Records per page' set to 15, '1 Of 1' records, and a 'Go' button. There is also a 'Lock Columns' dropdown set to 0. The main area is a table with the following columns: 'Authorization Status', 'Record Status', 'Branch Code', 'External System', 'Interface Code', and 'Interface Type'. The table is currently empty. At the bottom right of the window is an 'Exit' button.

You can click 'Search' button to view all the interface records of your bank. You can filter your search based on any of the following criteria:

### **Authorization Status**

Select the authorization status of the Interface definition you want to view the details from the drop-down list. The options are:

- Authorized
- Unauthorized

### **Branch code**

Select the branch code belonged to the interface details from the option list.

### **Interface code**

Select the interface code belonged to the interface details from the option list

### **Record Status**

Select the record status of the interface details from the drop-down list. The options are:

- C – Closed
- O - Open

### **External System**

Select the name of the external system belonged to the interface details from the option list.

### **Interface Type**

Select the type of interface from the option list as incoming or outgoing.

When you click 'Search' button the records matching the specified search criteria are displayed. For each record fetched by the system based on your query criteria, the following details are displayed:

- Authorization Status
- Record Status
- Branch Code
- External System
- Interface Code
- Interface Type

#### **2.14.4.1 Search Functionalities**


The search functions available are:

- **Advanced** – Click **Advanced** to specify queries with logical operators such as AND, OR and NOT.
- **Reset** – Click **Reset** to empty the values in the criteria fields, so that you may begin a new search.
- **Query** – After specifying your search criteria click **Query** to view the list of results which match your search criteria.
- **Refresh** – Click **Refresh** to refresh the list of results.



## 2.14.5 Maintaining AUDF (ASCII User Defined Function) Details

You can maintain the AUDF (ASCII User Define Function) details in the 'AUDF Maintenance' screen. You can invoke this screen by typing 'GIDAUDFM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.



The screenshot shows the 'AUDF Maintenance' application window. The title bar includes a diamond icon, the text 'AUDF Maintenance', and standard window controls. Below the title bar is a toolbar with 'New' and 'Enter Query' buttons. The main area contains four input fields: 'AUDF Name \*', 'Description', 'Unit Name \*', and 'AUDF Type \*'. The 'AUDF Type \*' field is a dropdown menu currently showing 'Message'. To the right of the 'Unit Name \*' field is a small yellow speech bubble icon. At the bottom of the window is a dark blue status bar with the following text: 'Input By Date Time', 'Authorized By Date Time', 'Modification Number', and two checkboxes labeled 'Authorized' and 'Open'.

Specify the following AUDF details in this screen.

### **AUDF Name**

Specify the name of the AUDF here.

### **Description**

Specify a description for the AUDF here.

### **Unit Name**

Specify the invoked function name here.

### **AUDF Type**

Select the AUDF types from the drop-down list. The following options are available:

- Message
- Component
- Record
- Field

## 2.14.6 Viewing AUDF Summary Details

You can view AUDF details maintained in the system using 'AUDF Summary' screen. You can invoke this screen by typing 'GISAUDFM' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a web application window titled 'Summary'. At the top, there are 'Advanced Search' and 'Reset' buttons. Below this, there are four search filters: 'Authorization Status' (a dropdown menu), 'Record Status' (a dropdown menu), 'AUDF Name' (a text input field with a search icon), and 'Description' (a text input field with a search icon). Below the filters is a pagination bar showing 'Records per page' set to 15, and buttons for 'First', 'Previous', '1 Of 1', 'Next', 'Last', and 'Go'. Below the pagination bar is a table with a blue header row containing the following columns: 'Authorization Status', 'Record Status', 'AUDF Name', and 'Description'. The table body is currently empty. At the bottom of the window, there are two buttons on the left: 'Authoriza' and 'Record St', and an 'Exit' button on the right.

You can click 'Search' button to view all the AUDF records of your bank. You can filter your search based on any of the following criteria:

### Authorization Status

Select the authorization status of the AUDF you want to view the details from the drop-down list. The options are:

- Authorized
- Unauthorized

### Record Status

Select the record status of the AUDF from the drop-down list. The options are:

- C – Closed
- O - Open

### AUDF Name

Select the name of the AUDF from the option list.

### Description

Select the description of the AUDF from the option list.

When you click 'Search' button the records matching the specified search criteria are displayed. For each record fetched by the system based on your query criteria, the following details are displayed:

- Authorization Status
- Record Status
- AUDF Name
- Description

## 2.14.7 Maintaining Translation Details

You can maintain translation details required between the external system values to Oracle FLEXCUBE Values and vice Versa in the 'Translation Definition' screen. You can invoke this screen by typing 'GIDTRANS' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Translation Definition' application window. At the top, there are buttons for 'New' and 'Enter Query'. Below that is a 'Table Name \*' text box. The main area is titled 'Translate Parameter' and contains a table with two columns: 'In Parameter' and 'Out Parameter'. Each column has a text input field with a help icon. At the bottom of the window, there are fields for 'Input By Date Time', 'Authorized By Date Time', and 'Modification Number'. There are also checkboxes for 'Authorized' and 'Open'.

You can capture the following details here:

### Translation Name

Specify the translation name you want to keep for the set. The translation name gets linked to the interface field whose value needs to be translated during Interface Processing.

### Translation Parameters

The following details are specified here:

#### In Param

Specify the system value for the corresponding external systems value.

#### Out Param

Specify the external system's value for the corresponding Oracle FLEXCUBE value.

## 2.14.8 Viewing Translation Summary Details

You can view the translation details maintained in the system using 'Translation Summary' screen. You can invoke this screen by typing 'GISTRANS' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Translation Summary' application window. The window has a title bar with standard minimize, maximize, and close buttons. Below the title bar, there is a search bar with the following options: 'Search', 'Advanced Search', 'Reset', and 'Clear All'. Underneath the search bar, there are two dropdown menus: 'Authorization Status' and 'Record Status'. A text input field for 'Table Name' is also present. The main area displays a table with columns for 'Authorization Status', 'Record Status', and 'Table Name'. The table is currently empty. At the bottom right, there is an 'Exit' button.

You can click 'Search' button to view all the translation records of your bank. You can filter your search based on any of the following criteria:

### Authorization Status

Select the authorization status of the translation you want to view the details from the drop-down list. The options are:

- Authorized
- Unauthorized

### Record Status

Select the record status of the translation from the drop-down list. The options are:

- C – Closed
- O - Open

### Translation Name

Select the name of the translation from the option list.

When you click 'Search' button the records matching the specified search criteria are displayed. For each record fetched by the system based on your query criteria, the following details are displayed:

- Authorization Status
- Record Status
- Translation Name

### 2.14.8.1 Search Functionalities

The search functions available are:

- Advanced – Click **Advanced** to specify queries with logical operators such as AND, OR and NOT.

- **Reset** – Click **Reset** to empty the values in the criteria fields, so that you may begin a new search.
- **Query** – After specifying your search criteria click **Query** to view the list of results which match your search criteria.
- **Refresh** – Click **Refresh** to refresh the list of results.

### 2.14.9 Maintaining CRC Algorithm Details

Generic Interface supports CRC-32 and Adler-32 Checksum algorithms for generating CRC value of the file. Other CRC components which are developed in Java and PL/SQL are also supported by GI using the 'CRC Maintenance' screen.

You can invoke this screen by typing 'GIDCRCFN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

You can write the invocation stub along with the CRC component details here:

#### **CRC Name**

Specify the CRC Algorithm used to calculate the CRC value for the file.

#### **Description**

Specify the description of the CRC Algorithm here.

#### **Invocation Stub**

Specify the stub to invoke the CRC generation component.

## 2.14.10 Viewing CRC Summary Details

You can view the CRC details maintained in the system using 'CRC Summary' screen. You can invoke this screen by typing 'GIDCRCFN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows a web application window titled "CRC Maintenance". At the top, there is a menu bar with "New" and "Enter Query". Below the menu bar, there are three input fields: "CRC Name \*" (with a red asterisk), "Description", and "Invocation Stub". The bottom of the window is a light blue footer containing labels for "Maker", "Checker", "Date Time:", "Mod No", "Record Status", and "Authorization Status", along with an "Exit" button.

You can click 'Search' button to view all the CRC records of your bank. You can filter your search based on any of the following criteria:

### Authorization Status

Select the authorization status of the CRC algorithm from the drop-down list. The options are:

- Authorized
- Unauthorized

### CRC Name

Select the name of the CRC algorithm from the option list.

### Record Status

Select the record status of the CRC algorithm from the drop-down list. The options are:

- C – Closed
- O - Open

### Description

Select the description of the CRC algorithm from the option list.

When you click 'Search' button the records matching the specified search criteria are displayed. For each record fetched by the system based on your query criteria, the following details are displayed:

- Authorization Status
- Record Status
- CRC Name
- Description

## 2.14.10.1 Search Functionalities

The search functions available are:

- **Advanced** – Click **Advanced** to specify queries with logical operators such as AND, OR and NOT.
- **Reset** – Click **Reset** to empty the values in the criteria fields, so that you may begin a new search.
- **Query** – After specifying your search criteria click **Query** to view the list of results which match your search criteria.
- **Refresh** – Click **Refresh** to refresh the list of results.

## 2.15 Process Definition

This section contains the following topics:

- [Section 2.15.1, "Maintaining Process Codes"](#)

### 2.15.1 Maintaining Process Codes

You can maintain the process codes using the 'Process Definition' screen. You can invoke this screen by typing 'SMDPRCDE' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Fields						
Maker	SYSTEM	Date Time:	1998-01-01	Mod No	1	Record Status Open
Checker	SYSTEM	Date Time:	1998-01-01	Authorization	Authorized	Status

You can specify the following here:

#### **Process Code**

Specify a unique code for the process.

#### **Description**

Enter an appropriate description of the process.

After entering the details, click the 'Save' button.

## 2.16 Reporting Parameters Maintenance

This section contains the following topic:

- [Section 2.16.1, "Maintaining Report Spool Path"](#)

### 2.16.1 Maintaining Report Spool Path

You can maintain a location to spool the reports for a specific branch using 'Reporting System – Parameters' screen. You can invoke this screen by typing 'RPDRPRAM' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

Maker	Date Time:	Mod No	Record Status
Checker	Date Time:		Authorization Status

Exit

Here, you need to specify the following details:

#### **Branch**

The system displays the branch for which you are maintaining the spool path. However, you cannot modify it.

#### **Spool Path**

Specify the location to which the reports should be spooled. The system stores the generated reports into this location, if you have selected 'Spool' in the 'Printing Preferences' screen.

#### **Spool History Path**

Specify the spool history path. This is the generation where the system saves the generated report. It is usually the same as the spool path.

#### **Time Out**

Specify the time span within which you wish to complete the process. The system reports if it takes longer time to generate it.

#### **Server Report Path**

This is the location where the system stores the report, if you have selected the option 'View' in the 'Printing Preferences' screen.



## 2.17 Maintaining Amount Text

You can describe the amounts printed on account statements, messages, advices, etc., in words, for the benefit of your customers. To describe 'amounts' in a specific language, you have to maintain the verbal equivalents of numerals in the language. You can maintain verbal equivalents of numerals in the 'Amount Text Maintenance' screen.

You can invoke this screen by typing 'STDAMTMN' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

The screenshot shows the 'Amount Text Maintenance' application window. At the top, there are 'New' and 'Enter Query' buttons. Below that are input fields for 'Language Code \*' and 'Description'. The 'Text' section contains a table with the following structure:

Amount *	Description	Prefix One
		<input checked="" type="checkbox"/>

The 'Currencies' section contains a table with the following structure:

Currency Code *	Pre Decimal	Post Decimal	Final Text	Text Before	Fractions
				<input checked="" type="checkbox"/>	<input type="checkbox"/>

The 'Fields' section at the bottom lists: Maker, Checker, Mod No, Date Time, Date Time, Record Status, and Authorization Status. An 'Exit' button is located in the bottom right corner.

Amount translation details can be maintained as one time maintenance at the time Oracle FLEXCUBE is installed at your bank. Once maintained, the amount descriptions printed on account statements, and other messages, will be described according to your specifications in this screen.

### Language

You can maintain verbal equivalents of numerals in any language that Oracle FLEXCUBE supports. This means that you can maintain the verbal equivalents of numerals in as many languages as you generate messages.

### Text

You must describe the following numerals in the Description field (in the language that you specify in the Language field):

- 1, 2, 3, upto 10
- 20, 30, 40, 50, 60, 70, 80, and 90
- 100

- 1,000
- 10,000
- 100,000
- 1,000,000
- 10,000, 000, and so on

In certain languages, One thousand, One million, and so on are expressed, simply, as 'thousand', and 'million'. If you are defining verbal equivalents of amounts in such a language, do not choose the 'Prefix One' option. Statements and messages printed in such a language will describe amounts such as '1000', simply, as 'thousand'.

Choose the 'Prefix One' option, if you would like amounts such as '1000' described as 'One thousand'.

### **Currencies**

In this screen, you can also describe the pre-decimal and the post-decimal units of a currency in different languages. Enter the verbal equivalent of the 'pre' and 'post' decimal units of a currency in the Pre-Decimal and Post-Decimal fields respectively. For example, if you would like to describe the decimal units of USD, enter:

6. The currency in the Currency field
7. The pre-decimal description as 'Dollars'
8. The post-decimal description as 'Cents'
9. Final Text to be attached to the currency.

You can opt to prefix, or suffix, an amount with its currency. If you would like the suffix an amount with its currency, do not choose the 'Text Before' option. If you would like to prefix an amount with its currency, choose the 'Text Before' option.

For example, if you would like to describe USD 1000, as Dollars One Thousand, choose the 'Text Before' option.

## **2.18 Dynamic Package - DML Execution**

You can synchronize the dynamic packages and DML statements which have to get propagated to the PDBs from Aproot through 'Dynamic Package - DML Execution Screen'.

You can invoke this screen by typing 'CODDYNCL' in the field at the top right corner of the Application tool bar and clicking on the adjoining arrow button.

You can specify the following here:

### Module Code

Specify the module code for which the dynamic packages and DML statements have to get propagated to the PDB from Approot. Alternatively, you can select the module code from the option list. The list displays all valid module codes maintained in the system.

### Function Id

The system displays the function ID based on the module code selected.

### Status

Select any of the following options:

- Unprocessed - Select this to fetch the unprocessed records in the PDB and proceed with processing.
- Processed - Select this to view the recent synchronized records in PDB.

After selecting the status, click 'Populate' button to fetch the list of records to be processed or records that are already processed based.

On selecting the status as 'Unprocessed' and upon clicking the 'Populate' button, you can view the list of records which are yet to be compiled in the PDB. These records can be processed on clicking the button 'Process All Records'. The system displays an information message once processing of all the records are completed. You cannot do any other operation after processing the records. The action buttons will be disabled.

You can select the Status as 'Processed' to view the list of processed records. Status column will depict the processed status of the records. Error records can be viewed from the sub screen 'Error Details' available in the main screen.

## 2.19 Maintaining Alternate Risk Free Rates

You can maintain rate in 'RFR Rate Input screen'. You can invoke this screen by typing 'CFDRFRRT' in the field at the top right corner of the Application tool bar and clicking the adjoining arrow button.

### Rate Code

Enter a rate code to identify the Risk Free Rates (RFR) you are defining. For example: SOFR.

### Rate Description

Enter a brief description to identify the rate code being defined.

### Type

Choose the type of Maintenance:

- Rate
- Index Value

### Rate Code Type

The system displays the rate code type maintained in the **CFDFRTCD** screen.

### Currency

Specify the currency for this rate code.

You can choose the appropriate one from the adjoining option list that displays all valid currency codes for the rate code maintained in the system.

### Rate Received Date

The date on which our system received the RFR Rate or Index value.

### Effective Date

Each rate that you define for a Rate Code and Currency combination should have an Effective Date associated with it.

This is the date on which the rate comes into effect. Once a rate comes into effect, it is applicable till a rate with another Effective Date is given for the same Rate Code and Currency combination.

### Rate/Index Value

Specify the interest rate or index value.

### Rate Applicable Days

The number of days the defined rate is applicable.

### Percentile Rate Details

Denotes the monthly/quarterly/ yearly/average rate details received from SOFR.

## 2.20 Customer Account Entitlement Group Maintenance

You can invoke the 'Customer Account Entitlement Group Maintenance' screen by typing 'STDCRAEG' in the field at the top right corner of the Application toolbar and clicking on the adjoining arrow button.

The screenshot shows a window titled "Customer Account Entitlement Group Maintenance" with a standard Windows-style title bar (minimize, maximize, close buttons). Below the title bar is a menu bar with "New" and "Enter Query" options. The main area contains a form with the following fields:

- Domain \***: A drop-down menu.
- Entitlement Group \***: A text input field.
- Entitlement Group Description**: A larger text input area.

At the bottom of the window is a status bar with the following fields:

Maker	Date Time:	Mod No	Record Status	Ok Exit
Checker	Date Time:		Authorization Status	

You can specify the following fields:

### Domain

Select the Domain from the drop-down list. The values are:

- Payment
- Branch

### Entitlement Group

Specify the Group code. The Group Code is an alphanumeric field of 30 characters length.

### Entitlement Group Description

Specify a brief description of the entitlement group. This field an alphanumeric field of 255 characters length.

A pre-defined group code of each entitlement group is provided as below:

<b>Entitlement Group</b>	<b>Group Code</b>	<b>Group Description</b>
PAYMENT_ENTITLE- MENT_GROUP	*.*	All Entitlements
BRANCH_ENTITLE- MENT_GROUP	*.*	All Entitlements

---

## 3. Function ID Glossary

### C

CFDFLTRI .....	2-36
CFDFRTCD .....	2-37
CFDRFRRT .....	2-119
CFSFRTCD .....	2-37
CODDYNCL .....	2-119
CYDCDEFE .....	2-11
CYDCRATY .....	2-29
CYDPOGL .....	2-23
CYSCCYPR .....	2-28
CYSCDEFE .....	2-24

### G

GIDAUDFM .....	2-109
GIDCRCFN .....	2-113, 2-114
GIDFILOG .....	2-98
GIDIFPRS .....	2-97
GIDIFTDF .....	2-99
GIDPARAM .....	2-95
GIDTRANS .....	2-111
GISAUDFM .....	2-110
GISIFTDF .....	2-107
GISTRANS .....	2-112
GLDCLSMT .....	2-86

### I

ISDBICDE .....	2-59
ISDBICPB .....	2-63
ISDBICPU .....	2-80
ISDBKDIR .....	2-84
ISDBKDPL .....	2-71
ISDESBAN .....	2-77
ISDIBNPL .....	2-74
ISSBICDE .....	2-62
ISSBICPB .....	2-64
ISSBKDIR .....	2-86
ISSBKDPL .....	2-72
ISSEBANP .....	2-76, 2-77
ISSESBAN .....	2-79

ISSIBNPL .....	2-75
----------------	------

### M

MIDGRPMT .....	2-89
MIDXCODE .....	2-90
MIDXPOLD .....	2-92

### R

RPDRPRAM .....	2-116
----------------	-------

### S

SMDPRCDE .....	2-115
STDAMTMN .....	2-117
STDBKMNT .....	2-67
STDCCHOL .....	2-34
STDCIFCR .....	2-43
STDCNMNT .....	2-9
STDCRACC .....	2-46
STDCRAEG .....	2-121
STDCRBANK .....	2-2
STDCRBRN .....	2-3
STDCRCLN .....	2-49
STDCRCOL .....	2-50
STDCRFAC .....	2-54
STDCRGLM .....	2-41
STDCRLIB .....	2-58
STDCRLIK .....	2-57
STDCRMCA .....	2-48
STDCRPOL .....	2-53
STDCRTRN .....	2-42
STDECAMT .....	2-43
STDHSTCD .....	2-5
STSBKMNT .....	2-70
STSCIFCR .....	2-45
STSHSTCD .....	2-6

### U

UDDFFLMT .....	2-94
UDDUDFMT .....	2-93