

**Oracle® Communications**

**Diameter Signaling Router**

Subscriber Data Server Cloud Installation Guide

Release 8.6.0.0.0

F56200-01

April 2022

**ORACLE®**

Oracle Communications Diameter Signaling Router Subscriber Data Server Cloud Installation Guide, Release 8.6.0.0.0

Copyright © 2022 Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group. Windows® 7 and Windows® XP are trademarks or registered trademarks of Microsoft Corporation.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.



**CAUTION:** MOS (<https://support.oracle.com>) is your initial point of contact for all product support and training needs. A representative at Customer Access Support (CAS) can assist you with MOS registration.

Call the CAS main number at 1-800-223-1711 (toll-free in the US), or call the Oracle Support hotline for your local country from the list at <https://www.oracle.com/us/support/contact/index.html>.

See more information on My Oracle Support (MOS) in the Appendix F:

## Table of Contents

<b>1. Introduction</b>	<b>7</b>
1.1 References	7
1.2 Acronyms	7
1.3 Assumptions	8
1.4 XML Files	8
1.5 How to Use This Document	8
<b>2. Application Installation</b>	<b>9</b>
2.1 Installation Prerequisites	9
2.2 Activity Logging	9
2.3 Create SDS Guests (VMware)	9
2.4 Create SDS Guests	10
2.5 Create SDS Guests (OVM-S/OVM-M)	15
2.6 Configure Virtual Machines	18
<b>3. Configuration Procedures</b>	<b>26</b>
3.1 Configure SDS NOAM Servers (1 <sup>st</sup> Site Only)	26
3.2 OAM Pairing (1st SDS NOAM Site Only)	35
3.3 Query Server Installation (All SDS NOAM Sites)	44
3.4 OAM Installation for DR SDS NOAM Site (Optional)	51
3.5 OAM Pairing for DR SDS NOAM Site (Optional)	58
3.6 OAM Installation for DP-SOAM Sites (All DP-SOAM Sites)	64
3.7 OAM Pairing for DP-SOAM Sites (All DP-SOAM Sites)	71
3.8 DP Installation (All DP-SOAM Sites)	75
3.9 Configure ComAgent	83
3.10 Backups and Disaster Prevention	86
3.11 Backups and Disaster Prevention	86
3.12 Configure the Desired MTU value	90
<b>Appendix A. Create an XML file for Installing SDS Network Elements</b>	<b>92</b>
<b>Appendix B. List of Frequently Used Time Zones</b>	<b>95</b>
<b>Appendix C. Common KVM/OpenStack Tasks</b>	<b>97</b>
Appendix C.1 Import an OVA File	97
Appendix C.2 Create a Network Port	98
Appendix C.3 Create and Boot OpenStack Instance	99
Appendix C.4 Configure Networking for OpenStack Instance	100
<b>Appendix D. Application VIP Failover Options (OpenStack)</b>	<b>101</b>
Appendix D.1 Application VIP Failover Options	101
Appendix D.2 Allowed Address Pairs	102
Appendix D.3 OpenStack Configuration Requirements	103
Appendix D.4 After a VM Instance has been Booted: Allowed Address Pairs	103
Appendix D.5 Before a VM Instance has been Booted: Allowed Address Pairs	104
Appendix D.6 Disable Port Security	105

Appendix D.7	After a VM Instance has been Booted: Port Security .....	105
Appendix D.8	Before a VM Instance has been Booted: Port Security .....	106
Appendix D.9	Managing Application Virtual IP Addresses within VM Instances .....	107
<b>Appendix E.</b>	<b>Common OVM-Manager Tasks (CLI) .....</b>	<b>108</b>
Appendix E.1	Set Up the Server.....	108
Appendix E.2	Server Pool .....	114
<b>Appendix F.</b>	<b>My Oracle Support (MOS) .....</b>	<b>115</b>
<b>Appendix G.</b>	<b>Emergency Response .....</b>	<b>116</b>
<b>Appendix H.</b>	<b>Locate Product Documentation on the Oracle Help Center .....</b>	<b>117</b>

## List of Tables

Table 1. Acronyms .....	7
Table 2. SDS XML SDS Network Element Configuration File (IPv4) .....	92
Table 3. SDS XML SDS Network Element Configuration File (IPv6) .....	93
Table 4. List of Selected Time Zone Values .....	95

## List of Figures

Figure 1. Neutron High-Level Data Model .....	101
---	-----

## 1. Introduction

This document describes how to install the Oracle® Communications Subscriber Data Server (SDS) within a customer network. It makes use of the AppWorks 7.5 network installation and is intended to cover the initial network configuration steps for a SDS/Query Server NE for production use as part of the DSR solution.

This document only describes the SDS product SW installation on a virtualized solution into VMs hosted by the VMWare, KVM, and OVM-S hypervisors. It does not cover hardware installation, site survey, customer network configuration, IP assignments, customer router configurations, or the configuration of any device outside of the SDS virtual machines.

### 1.1 References

- [1] [DSR Cloud Benchmarking Guide](#), F12357-01
- [2] [Oracle VM Concepts Guide](#), E64081-09, Release 3.4

### 1.2 Acronyms

**Table 1. Acronyms**

Acronym	Definition
CSV	Comma Separated Values
DR	Disaster Recovery
DP	Database Processor
IMI	Internal Management Interface
IP	Internet Protocol
NAPD	Network Architecture Planning Document
NE	Network Element
NOAM	Network Operations, Administration, and Maintenance
OS	Operating System
OVM-M	Oracle VM Manager
OVM-S	Oracle VM Server
POC	Point of Contact
PSE	Professional Services Engineer
SDS	Subscriber Data Server
SOAM	Systems Operations, Administration & Maintenance
TPD	Tekelec Platform Distribution (Linux OS)
VIP	Virtual IP
VM	Virtual Management
XMI	External Management Interface

### 1.3 Assumptions

This procedure assumes the following:

- The user has reviewed the latest Customer specific Network Architecture Planning document and has received assigned values for all requested information related to SDS, DR SDS NO, Query Server, DP-SOAM, and DP installation.
- The user has taken assigned values from the latest Customer specific Network Architecture Planning document and used them to compile XML files (See Create an XML file for Installing SDS Network Elements) for each SDS and DP-SOAM site's NE before attempting to execute this procedure.
- The user conceptually understands DSR topology and SDS network configuration as described in the latest Customer specific Network Architecture Planning document.
- The user has at least an intermediate skill set with command prompt activities on an Open Systems computing environment such as Linux or TPD.

### 1.4 XML Files

The XML files compiled for installation of the each of the SDS and DP-SOAM site's NE must be maintained and accessible for use in Disaster Recovery procedures. The Oracle Professional Services Engineer (PSE) provides a copy of the XML files used for installation to the designated Customer Operations POC. **The customer is ultimately responsible for maintaining and providing the XML files to Oracle's Customer Service if needed for use in Disaster Recovery operations.**

### 1.5 How to Use This Document

Although this document is primarily to be used as an initial installation guide, its secondary purpose is as a reference for disaster recovery procedures. When executing this document for either purpose, there are a few points to help ensure the user understands the document's intent. These points are as follows:

- Before beginning a procedure, completely read the instructional text (it will appear immediately after the Section heading for each procedure) and all associated procedural WARNINGS or NOTES.
- Before execution of a STEP within a procedure, completely read the left and right columns including any STEP specific WARNINGS or NOTES.

If a procedural step fails to execute successfully, stop and contact Oracle's Help Center for assistance before attempting to continue. See Appendix F for information on contacting My Oracle Support (MOS).



## 2. Application Installation

Installing the SDS product is a task that requires multiple installations of varying types. This document only covers the necessary configuration required to complete product installation. Refer to the online help or contact the Oracle Help Center for assistance with post installation configuration options.

### 2.1 Installation Prerequisites

The following items/settings are required to perform installation:

- A laptop or desktop computer equipped as follows;
  - Administrative privileges for the OS.
  - An approved web browser.
- TPD **admusr** user password.

### 2.2 Activity Logging

All activity while connected to the system should be logged using a convention that notates the **Customer Name**, **Site/Node** location, **Server hostname** and the **Date**. All logs should be provided to Oracle Communications for archiving post installation.

### 2.3 Create SDS Guests (VMware)

#### Procedure 1. Create SDS Guests from OVA (VMWare)

Step	Procedure	Description
1. <input type="checkbox"/>	<b>Cloud Client:</b> Add SDS OVA image	1. Launch the <b>Cloud Client</b> of your choice. 2. Add the <b>SDS OVA image</b> to the cloud catalog or repository. Follow the instructions provided by the cloud solutions manufacturer.
2. <input type="checkbox"/>	<b>Cloud Client:</b> Create the SDS VM, from the OVA image	1. Browse the library or repository where you placed the <b>OVA image</b> . 2. Deploy the OVA image using Cloud Client or the Cloud Web Client. 3. Name the <b>SDS NOAM VM</b> and select the datastore.
3. <input type="checkbox"/>	<b>Cloud Client:</b> Configure resources for the SDS NOAM-A VM	Configure the <b>SDS NOAM VM</b> as defined in [1] DSR Cloud Benchmarking Guide for the <b>SDS NOAM</b> using the Cloud Client or the Cloud Web Client.
4. <input type="checkbox"/>	<b>Cloud Client:</b> Power on SDS NOAM-A VM	Use the Cloud Client or Cloud Web Client to power on the <b>SDS NOAM-A VM</b> .

**Procedure 1. Create SDS Guests from OVA (VMWare)**

Step	Procedure	Description
5. <input type="checkbox"/>	<b>Cloud Client:</b> Configure SDS NOAM-A	<ol style="list-style-type: none"> <li>1. Access the SDS NOAM-A VM console using the Cloud client or Cloud web client.</li> <li>2. Login as <b>admusr</b>.</li> <li>3. Set the <b>&lt;ethX&gt;</b> device:   <b>Note:</b> Where <b>ethX</b> is the interface associated with the <b>XMI</b> network.   <pre>\$ sudo netAdm add --device=&lt;ethX&gt; --address=&lt;IP Address in External management Network&gt; --netmask=&lt;Netmask&gt; --onboot=yes --bootproto=none</pre> </li> <li>4. Add the default route for <b>ethX</b>:   <pre>\$ sudo netAdm add --route=default --gateway=&lt;gateway address for the External management network&gt; --device=&lt;ethX&gt;</pre> </li> </ol> <p><b>Note:</b> When reconfiguring virtual NICs under VMware, the proper procedure is to remove the UDEV rules file (/etc/udev/rules.d/70-persistent-net.rules), shut down the guest and remove the interfaces. Power on the VM, then add the interfaces one by one, in the desired order of enumeration, each time clicking « OK » to get VMware to instantiate the device.</p>
6. <input type="checkbox"/>	Verify network connectivity	<p>Ping the <b>default</b> gateway.</p> <pre>\$ ping -c3 &lt;gateway address for the External management network&gt;</pre>
7. <input type="checkbox"/>	Repeat steps this procedure for each server before continuing to the next procedure (for example, NOAM-A, NOAM-B, DR SDS Servers, Query Server, DP).	

**2.4 Create SDS Guests****Procedure 2. Create SDS Guests from OVA (KVM/OpenStack)**

Step	Procedure	Description
1. <input type="checkbox"/>	Preparation	<ol style="list-style-type: none"> <li>1. Create instance flavors.             Use the [1] DSR Cloud Benchmarking Guide values to create flavors for each type of VM. Flavors can be created with the Horizon GUI in the Admin section, or with the <b>nova flavor-create</b> command line tool. Make the flavor names as informative as possible. As flavors describe resource sizing, a common convention is to use a name like <b>0406060</b> where the first two figures (04) represent the number of virtual CPUs, the next two figures (06) might represent the RAM allocation in GB and the final three figures (060) might represent the disk space in GB.</li> <li>2. If using an Intel 10 Gigabit Ethernet ixgbe driver on the host nodes, please note that the default LRO (Large Receive Offload) option must be disabled on the host command line. Please see the Intel release notes for more details.   <pre>\$ sudo ethtool -K &lt;ETH_DEV&gt; lro off</pre> </li> </ol>

**Procedure 2. Create SDS Guests from OVA (KVM/OpenStack)**

Step	Procedure	Description
2. □	Add SDS OVA image	<ol style="list-style-type: none"> <li>Copy the OVA file to the OpenStack control node.  <pre>\$ scp SDS-x.x.x.ova admusr@node:~</pre> </li> <li>Log into the OpenStack control node.  <pre>\$ ssh admusr@node</pre> </li> <li>In an empty directory unpack the OVA file using <b>tar</b>.  <pre>\$ tar xvf SDS-x.x.x.ova</pre> </li> <li>One of the unpacked files will have a <b>.vmdk</b> suffix. This is the VM image file that must be imported.  <pre>SDS-x.x.x-disk1.vmdk</pre> </li> <li>Source the OpenStack <b>admin</b> user credentials.  <pre>\$ . keystone_admin</pre> </li> <li>Select an informative name for the new image.  <pre>sds-x.x.x-original</pre> <p><b>Note:</b> To use VMDK format, perform step 7; to use QCOW2 format, go to steps 8 and 9.</p> </li> <li>Import the image using the <b>glance</b> utility from the command line.  <pre>\$ glance image-create --name sds-x.x.x-original --is-public True --is-protected False --progress --container-format bare --disk-format vmdk --file SDS-x.x.x-disk1.vmdk</pre> <p>This process takes about 5 minutes depending on the underlying infrastructure. This complete the VMDK format, go to step 3.</p> </li> <li>Convert VMDK to QCOW2 format by using the <b>qemu-img</b> tool to create a qcow2 image file using this command.  <pre>qemu-img convert -f vmdk -O qcow2 &lt;VMDK filename&gt; &lt;QCOW2 filename&gt;</pre> <p>Example:  <pre>qemu-img convert -f vmdk -O qcow2 SDS-82_12_0.vmdk SDS-82_12_0.qcow2</pre> </p> <p><b>Note:</b> Install the <b>qemu-img</b> tool (if not already installed) using this yum command.  <pre>sudo yum install qemu-img</pre> </p> </li> <li>Import the converted QCOW2 image using the <b>glance</b> utility from the command line.  <pre>\$ glance image-create --name sds-x.x.x-original --is-public True --is-protected False --progress --container-format bare --disk-format qcow2 --file SDS-x.x.x-disk1.qcow2</pre> <p>This process takes about 5 minutes depending on the underlying infrastructure.</p> </li> </ol>

**Procedure 2. Create SDS Guests from OVA (KVM/OpenStack)**

Step	Procedure	Description
3. <input type="checkbox"/>	Name the new VM instance	<ol style="list-style-type: none"> <li>1. Create an informative name for the new instance: <b>SDS-NOAM-A</b>.</li> <li>2. Review the network interface recommendations provided in [1] DSR Cloud Benchmarking Guide.</li> </ol>
4. <input type="checkbox"/>	<b>OpenStack Control Node:</b> Create and boot the VM instance from the glance image	<ol style="list-style-type: none"> <li>1. Get the following configuration values. <ol style="list-style-type: none"> <li>a. The image ID.  <pre>\$ glance image-list</pre> <p><b>Example output of image ID:</b> 811f0181-6e66-4cf0-9eb7-8058d86edf05</p> </li> <li>a. The flavor ID.  <pre>\$ nova flavor-list</pre> </li> <li>b. The network ID(s)  <pre>\$ neutron net-list</pre> <p><b>Example output of network ID:</b> cb2a0b22-2383-462d-bce5-73f3f5bb752d</p> </li> <li>c. An informative name for the instance.  <pre>SDS-NOAM-A</pre> <pre>SDS-NOAM-B</pre> </li> </ol> </li> <li>2. Create and boot the VM instance.   <p>The instance must be owned by the DSR tenant user, not the admin user. Source the credentials of the DSR tenant user and issue the following command. Use one <b>--nic</b> argument for each IP/interface.</p> <p><b>Note:</b> IPv6 addresses should use the <b>v6-fixed-ip</b> argument instead of <b>v4-fixed-ip</b>.</p> <pre>\$ nova boot --image &lt;image ID&gt; --flavor &lt;flavor id&gt; --nic net-id=&lt;first network id&gt;,v4-fixed-ip=&lt;first ip address&gt; --nic net-id=&lt;second network id&gt;,v4-fixed-ip=&lt;second ip address&gt; --config-drive true &lt;instance name&gt;</pre> </li> <li>3. View the newly created instance using the nova tool to verify the new instance has been booted.   <pre>\$ nova list   grep -i (xmi address)</pre> <p>The VM takes approximately 5 minutes to boot and may be accessed through both network interfaces and the Horizon console tool.</p> </li> </ol>

**Procedure 2. Create SDS Guests from OVA (KVM/OpenStack)**

Step	Procedure	Description
5. <input type="checkbox"/>	<b>OpenStack Control Node:</b> Configure VIP (optional)	<p><b>Note:</b> Refer to Appendix D.1 Application VIP Failover Options (OpenStack) for more information on VIP.</p> <p>If an NOAM/SOAM VIP is needed, execute the following commands:</p> <ol style="list-style-type: none"> <li>1. Find the port ID associated with the instance's network interface.           <pre>\$ neutron port-list</pre> <p><b>Example output of port ID:</b> aed2522e-cf52-4aa4-9e12-4acab7f8df04</p> </li> <li>2. Add the VIP IP address to the address pairs list of the instance's network interface port.           <pre>\$ neutron port-update &lt;Port ID&gt; --allowed_address_pairs list=true type=dict ip_address=&lt;VIP address to be added&gt;</pre> </li> </ol>
6. <input type="checkbox"/>	Check if interface is configured	<p>If DHCP is enabled on Neutron subnet, VM configures the VNIC with the IP address provided in step 4. To verify, ping the XMI IP address provided with the <b>nova boot</b> command from step 4. :</p> <pre>\$ ping &lt;XMI-IP-Provided-During-Nova-Boot&gt;</pre> <p>If the ping is successful, ignore step 7. to configure the interface manually.</p>

**Procedure 2. Create SDS Guests from OVA (KVM/OpenStack)**

Step	Procedure	Description
7. <input type="checkbox"/>	<b>OpenStack Dashboard (Horizon):</b> Manually configure interface, if not already done (Optional)	<p><b>Note:</b> If the instance is already configured with an interface and has successfully pinged (step 6. ), then <b>ignore</b> this step to configure the interface manually.</p> <ol style="list-style-type: none"> <li>1. Log into the <b>Horizon</b> GUI as the tenant user.</li> <li>2. Go to the Compute/Instances section.</li> <li>3. Click on the <b>Name</b> field of the newly created instance.</li> <li>4. Select the Console tab.</li> <li>5. Login as the <b>admusr</b> user.</li> <li>6. Select an informative hostname for the new VM instance. SDS-NOAM-A SDS-SO2</li> <li>7. Configure the network interfaces, conforming to the OCDSR Network to Device Assignments defined in [1] DSR Cloud Benchmarking Guide. <pre>\$ sudo netAdm set --onboot=yes --device=eth0 --address=&lt;xmi port ip&gt; --netmask=&lt;xmi net mask&gt;</pre><pre>\$ sudo netAdm add --route=default --device=eth0 --gateway=&lt;xmi gateway ip&gt;</pre>Under some circumstances, it may be necessary to configure more interfaces. If netAdm fails to create the new interface (ethX) because it already exists in a partially configured state, perform the following actions. <pre>\$ cd /etc/sysconfig/network-scripts</pre><pre>\$ sudo mv ifcfg-ethX /tmp</pre>Keep ifcfg-ethX in /tmp until ethX is working correctly. Re-run the <b>netAdm</b> command. It creates and configures the interface in one action.</li> <li>8. Reboot the VM. It takes approximately 5 minutes for the VM to complete rebooting. <pre>\$ sudo init 6</pre>The new VM should now be accessible using both network and Horizon console.</li> </ol>
8. <input type="checkbox"/>	Verify network connectivity	Ping the <b>default</b> gateway. <pre>\$ ping -c3 &lt;gateway address for the External management network&gt;</pre>
9. <input type="checkbox"/>	Repeat these steps 3 through 8 for each server before continuing on to the next procedure (for example, NOAM-A, NOAM-B, DR Servers, Query Server, and DP).	

## 2.5 Create SDS Guests (OVM-S/OVM-M)


Procedure 3 imports the SDS image. This procedure requires values for these variables:

- <OVM-M IP> = IP address to access a sh prompt on the OVM server
- <URL to OVA> = link to a source for downloading the product image (.ova)
- <MyRepository name> = name of the repository in the OVM to hold the product image (.ova)

Execution of this procedure discovers and uses the values of these variables:

- <Virtual Appliance OVA ID>
- <OVA VM name\_vm\_vm>
- <OVM network id for (each subnet)>
- <OVM network name for (each subnet)>

### Procedure 3. Create SDS Guests From OVA (OVM-S/OVM-M) - Import SDS OVA and prepare for VM creation

Step	Procedure	Description
1. <input type="checkbox"/>	<b>Preparation:</b> Access command line of OVM	<p>Refer to Common OVM-Manager Tasks (CLI) in Appendix E for setting up the platform.</p> <ol style="list-style-type: none"> <li>1. Get the site-specific values for these variables (overwrite example). &lt;OVM-M IP&gt; = 100.64.62.221</li> <li>2. Use the respective value for &lt;OVM-M IP&gt; into the command. <code>ssh -l admin &lt;OVM-M IP&gt; -p 10000</code> Example: <code>ssl -l admin 100.64.62.221 -p 10000</code> Alternatively, use a terminal emulation tool like putty.</li> </ol> 

### Procedure 3. Create SDS Guests From OVA (OVM-S/OVM-M) - Import SDS OVA and prepare for VM creation

Step	Procedure	Description
2. <input type="checkbox"/>	<b>OVM-M CLI:</b> Import the OVA	<ol style="list-style-type: none"> <li>1. Get the site-specific values for these variables (overwrite example).            &lt;URL to OVA&gt; = <a href="http://10.240.155.70/iso/SDS/8.6/ova/SDS-8.6.0.0.0_95.14.0.ova">http://10.240.155.70/iso/SDS/8.6/ova/SDS-8.6.0.0.0_95.14.0.ova</a>            &lt;MyRepository name&gt; = XLab Utility Repo1</li> <li>2. Use the respective values for &lt;MyRepository name&gt; and &lt;URL to OVA&gt; into the command.  <pre>OVM&gt;importVirtualAppliance Repository name='&lt;MyRepository name&gt;' url="&lt;URL to OVA&gt;"</pre>           Example:  <pre>OVM&gt; importVirtualAppliance Repository name='XLab Utility Repo1' url=http://10.240.155.70/iso/SDS/8.6/ova/SDS- 8.6.0.0.0_95.14.0.ova</pre> </li> <li>3. Execute the command and validate success.</li> <li>4. Examine the screen results to find site-specific text for <b>variables</b> in these locations:            Command: <pre>importVirtualAppliance Repository name='XLab Utility Repo1' url=http://10.240.155.70/iso/SDS/8.6/ova/SDS- 8.6.0.0.0_95.14.0.ova Status: Success Time: 2017-04-18 15:23:31,044 EDT JobId: 1492543363365 Data:   id: 1128a1c6ce name: SDS-8.6.0.0.0_95.14.0.ova</pre> </li> <li>5. Use the respective values for values for these variables (overwrite example).            &lt;Virtual Appliance OVA ID&gt; = 1128a1c6ce</li> </ol>



### Procedure 3. Create SDS Guests From OVA (OVM-S/OVM-M) - Import SDS OVA and prepare for VM creation

Step	Procedure	Description
3. <input type="checkbox"/>	<b>OVM-M CLI:</b> Get the virtual appliance ID	<p>The virtual appliance OVA ID is used in later steps.</p> <ol style="list-style-type: none"> <li>Get the site-specific text for these variables (overwrite example). &lt;Virtual Appliance OVA ID&gt; = 1128a1c6ce</li> <li>Use the respective values for &lt;Virtual Appliance OVA ID&gt; into the command. <code>OVM&gt; show VirtualAppliance id=&lt;Virtual Appliance OVA id&gt;</code></li> </ol> <p>Example: <code>OVM&gt; show VirtualAppliance id=1128a1c6ce</code></p> <ol style="list-style-type: none"> <li>Execute the command and validate success.</li> <li>Examine the screen results to find site-specific text for <b>variables</b> in these locations: <b>Command:</b> <code>show VirtualAppliance id=1128a1c6ce</code> <b>Status:</b> Success <b>Time:</b> 2017-04-18 15:23:53,534 EDT <b>Data:</b> <code>Origin = <a href="http://10.240.155.70/iso/SDS/8.6/ova/SDS-8.6.0.0.0_95.14.0.ova">http://10.240.155.70/iso/SDS/8.6/ova/SDS-8.6.0.0.0_95.14.0.ova</a></code> <code>Repository = 0004fb0000030000da5738315337bfc7 [XLab Utility Repo01]</code> <code>Virtual Appliance Vm 1 = 11145510c0_vm_vm [vm]</code> <code>Virtual Appliance VirtualDisk 1 = 11145510c0_disk_disk1 [disk1]</code> <code>Id = 11145510c0 [SDS-8.6.0.0.0_95.14.0.ova]</code> <code>Name = SDS-8.6.0.0.0_95.14.0.ova</code> <code>Description = Import URL: <a href="http://10.240.155.70/iso/SDS/8.6/ova/SDS-8.6.0.0.0_95.14.0.ova">http://10.240.155.70/iso/SDS/8.6/ova/SDS-8.6.0.0.0_95.14.0.ova</a></code> <code>Locked = false</code></li> <li>Use the respective values for these variables (overwrite example). &lt;OVA VM name_vm_vm&gt; = 11145510c0_vm_vm</li> </ol>

### Procedure 3. Create SDS Guests From OVA (OVM-S/OVM-M) - Import SDS OVA and prepare for VM creation

Step	Procedure	Description									
4. <input type="checkbox"/>	<b>OVM-M CLI:</b> Determine the OVM network IDs (established during the platform installation)	<p><code>OVM&gt; list Network</code></p> <ol style="list-style-type: none"> <li>Execute the command and validate success.</li> <li>Examine the screen results to find the find site-specific OVM values for each subnet: <ul style="list-style-type: none"> <li>&lt;OVM network ID&gt;</li> <li>&lt;OVM network name&gt;</li> </ul> </li> <li>Note the entire screen results. Refer to this data in later steps.  Command: <code>list network</code>  Status: <code>Success</code>  Time: <code>2017-04-19 18:51:42,494 EDT</code>  Data: <pre> id:10486554b5 name:XSI-7 (10.196.237.0/25) id:10f4d5744c name:XMI-11 (10.75.159.0/25) id:10775cf4e5 name:IDIH Internal id:102e89a481 name:IMI Shared (169.254.9.0/24) id:c0a80500 name:192.168.5.0 id:10d8de6d9a name:XSI-6 (10.196.236.128/25) id:10806a91fb name:XSI-8 (10.296.237.128/25) id:10a7289add name:Control DHCP id:1053a604f0 name:XSI-5 (10.196.236.0/25) id:10345112c9 name:XMI-10 (10.75.158.128/25) </pre> </li> <li>Use the respective values for network ID variables (change the examples in table according to the values).</li> </ol> <table border="1"> <thead> <tr> <th></th> <th>OAM (XMI)</th> <th>Local (IMI)</th> </tr> </thead> <tbody> <tr> <td>&lt;OVM network name&gt;</td> <td>XMI-10</td> <td>IMI Shared</td> </tr> <tr> <td>&lt;OVM network ID&gt;</td> <td>10345112c9</td> <td>102e89a481</td> </tr> </tbody> </table>		OAM (XMI)	Local (IMI)	<OVM network name>	XMI-10	IMI Shared	<OVM network ID>	10345112c9	102e89a481
	OAM (XMI)	Local (IMI)									
<OVM network name>	XMI-10	IMI Shared									
<OVM network ID>	10345112c9	102e89a481									

## 2.6 Configure Virtual Machines

Procedure 4 creates virtual machines. Repeat this procedure for each of the SDS VM guests (NOAMs, DR Servers, SOAMs, Query servers, and DPs) that need to be created. This procedure requires values for these variables:

- <OVA VM name\_vm\_vm>
- <ServerPool name>
- <VM name>

- <OVM network ID for XMI>
- <OVM network ID for IMI>
- <URL for OVM GUI>
- <VM IP in XMI> from the NAPD
- <Gateway for XMI> from the NAPD
- <NetMask for XMI> from the NAPD

Execution of this procedure discovers and uses the values of these variables:

- <VM ID>
- <vCPUs Production>
- <VNIC 1 ID>
- <interface name> defined in [1] DSR Cloud Benchmarking Guide

#### Procedure 4. Configure each SDS VM

Step	Procedure	Description
1. <input type="checkbox"/>	<b>OVM-M CLI:</b> Create a VM for each guest from the VM in the OVA virtual appliance	<ol style="list-style-type: none"> <li>1. Get the site-specific text for these variables (overwrite example). &lt;OVA VM name_vm_vm&gt; = 11145510c0_vm_vm</li> <li>2. Use the respective values for &lt;OVA VM name&gt; into the command. <code>OVM&gt; createVmFromVirtualApplianceVm VirtualApplianceVm name=&lt;OVA VM name&gt;</code>  Example: <code>OVM&gt; createVmFromVirtualApplianceVm VirtualApplianceVm name=11145510c0_vm_vm</code></li> <li>3. Execute the command and validate success.</li> <li>4. Examine the screen results to find site-specific text for <b>variables</b> in these locations:  Command: <code>createVmFromVirtualApplianceVm VirtualApplianceVm name=11145510c0_vm_vm</code> Status: Success  Time: 2017-04-18 16:02:09,141 EDT  JobId: 1492545641976  Data:  id: 0004fb00000600004a0e02bdf9fc1bcd name:DSR-8.6.0.0.0_95.14.0.ova_vm</li> <li>5. Use the respective values for these variables (overwrite example). &lt;VM ID&gt; = 0004fb00000600004a0e02bdf9fc1bcd</li> </ol>

**Procedure 4. Configure each SDS VM**

Step	Procedure	Description
2. <input type="checkbox"/>	<b>OVM-M CLI:</b> Add the VM to the server pool	<ol style="list-style-type: none"> <li>1. Get the site-specific text for these variables (overwrite example).  <code>&lt;VM ID&gt; = 0004fb00000600004a0e02bdf9fc1bcd</code>  <code>&lt;ServerPool name&gt; = XLab Pool 01</code> </li> <li>2. Use the respective values for &lt;VM ID&gt; and &lt;ServerPool name&gt; into the command.  <code>OVM&gt; add Vm id=&lt;VM id&gt; to ServerPool name="&lt;ServerPool name&gt;"</code>    <b>Example:</b>  <code>OVM&gt; add Vm id=0004fb00000600004a0e02bdf9fc1bcd to ServerPool name="XLab Pool 01"</code> </li> <li>3. Execute the command and validate success.    <b>Command:</b> <code>add Vm id=0004fb0000060000beb93da703830d3c to ServerPool name="XLab Pool 01"</code>  <b>Status:</b> <code>Success</code>    <b>Time:</b> <code>2017-04-19 21:05:10,950 EDT</code>    <b>JobId:</b> <code>1492650310802</code> </li> </ol> <p><b>Note:</b> Refer to the Server Pool section in Appendix E.2 for more information.</p>

**Procedure 4. Configure each SDS VM**

Step	Procedure	Description												
3. <input type="checkbox"/>	<b>OVM-M CLI:</b> Edit VM to apply required profile/resources	<p>1. Get the site-specific text for these variables (overwrite example).</p> <pre>&lt;VM ID&gt; = 0004fb00000600004a0e02bdf9fc1bcd &lt;VM name &gt; = na-sdsnoam-na-2a &lt;vCPUs Production&gt; = 4</pre> <p>2. Refer to [1] DSR Cloud Benchmarking Guide for recommended resource.</p> <table border="1"> <thead> <tr> <th>VM Name</th> <th>vCPUs Lab</th> <th>RAM (GB) Lab</th> <th>vCPUs Production</th> <th>RAM (GB) Production</th> <th>Storage (GB) Lab and Production</th> </tr> </thead> <tbody> <tr> <td>Type of guest host</td> <td>#</td> <td>#</td> <td>#</td> <td>#</td> <td>#</td> </tr> </tbody> </table> <p>3. Use the respective values for &lt;VM ID&gt;, &lt;VM name&gt;, and &lt;vCPUs Production&gt; into the command.</p> <pre>OVM&gt; edit Vm id=&lt;VM id&gt; name=&lt;VM name&gt; memory=6144 memoryLimit=6144 cpuCountLimit=&lt;vCPUs Production&gt; cpuCount=&lt;vCPUs Production&gt; domainType=XEN_HVM description="&lt;VM name&gt;"</pre> <p>Example:</p> <pre>OVM&gt; edit Vm id=0004fb00000600004a0e02bdf9fc1bcd name=na-sdsnoam-na-2a memory=6144 memoryLimit=6144 cpuCountLimit=4 cpuCount=4 domainType=XEN_HVM description="na-sdsnoam-na-2a"</pre> <p>4. Execute the command and validate success.</p> <pre>Command: edit Vm id=0004fb00000600004a0e02bdf9fc1bcd name=na-sdsnoam-na-2a memory=6144 memoryLimit=6144 cpuCountLimit=4 cpuCount=4 domainType=XEN_HVM description="na-sdsnoam-na-2a" Status: Success Time: 2017-04-18 17:55:25,645 EDT JobId: 1492552525477</pre> <p>Now, the VM has a name and resources.</p>	VM Name	vCPUs Lab	RAM (GB) Lab	vCPUs Production	RAM (GB) Production	Storage (GB) Lab and Production	Type of guest host	#	#	#	#	#
VM Name	vCPUs Lab	RAM (GB) Lab	vCPUs Production	RAM (GB) Production	Storage (GB) Lab and Production									
Type of guest host	#	#	#	#	#									
4. <input type="checkbox"/>	<b>OVM-M CLI:</b> Determine VNIC ID	<p>1. Get the site-specific text for these variables (overwrite example).</p> <pre>&lt;VM name&gt; = na-sdsnoam-na-2a</pre> <p>2. Use the respective value for &lt;VM name&gt; into the command.</p> <pre>OVM&gt; show Vm name=&lt;VM name&gt;</pre> <p>Example:</p> <pre>OVM&gt; show Vm name=na-nsdsoam-na-2a</pre> <p>3. Execute the command and validate success.</p> <p>4. Examine the screen results to find site-specific text for <b>variables</b> in these locations:</p> <pre>Status = Stopped</pre>												

**Procedure 4. Configure each SDS VM**

Step	Procedure	Description
		<pre> Memory (MB) = 6144 Max. Memory (MB) = 6144   Processors = 4   Max. Processors = 4   Priority = 50   Processor Cap = 100   High Availability = No   Operating System = Oracle Linux 6   Mouse Type = PS2 Mouse   Domain Type = Xen HVM   Keymap = en-us   Start Policy = Use Pool Policy   Origin = <a href="http://10.240.155.70/iso/SDS/8.6/ova/SDS-8.6.0.0.0_95.14.0.ova">http://10.240.155.70/iso/SDS/8.6/ova/SDS-8.6.0.0.0_95.14.0.ova</a>   Disk Limit = 4   Huge Pages Enabled = No   Config File Absolute Path = 192.168.5.5:/storage/ovm01/repository/VirtualMachines/00 04fb00000600004a0e02bdf9fc1bcd/vm.cfg   Config File Mounted Path = /OVS/Repositories/0004fb0000030000da5738315337bfc7/Virtu alMachines/0004fb00000600004a0e02bdf9fc1bcd/vm.cfg   Server Pool = 0004fb00000200009148c8926d307f05 [XLab Pool 01]   Repository = 0004fb0000030000da5738315337bfc7 [XLab Utility Repo01]   Vnic 1 = 0004fb0000070000091e1ab5ae291d8a [Template Vnic]   VmDiskMapping 1 = 0004fb0000130000a1996c6074d40563 [Mapping for disk Id (79def426328a4127b5bf9f7ae53d3f48.img)]   VmDiskMapping 2 = 0004fb00001300002db3d4b67a143ab5 [Mapping for disk Id (EMPTY_CDROM)]   Restart Action On Crash = Restart   Id = 0004fb00000600004a0e02bdf9fc1bcd [na-sdsnoam-na- 2a]   Name = na-sdsnoam-na-2a   Description = na-sdsnoam-na-2a   Locked = false </pre>

**Procedure 4. Configure each SDS VM**

Step	Procedure	Description						
		<pre>DeprecatedAttrs = [Huge Pages Enabled (Deprecated for PV guest)]</pre> <p>5. Use the respective values for these variables (overwrite example).            &lt;VNIC 1 ID&gt; = 0004fb0000070000091e1ab5ae291d8a</p>						
5. <input type="checkbox"/>	Determine network interfaces for the type of guest host	<p>Refer to [1] DSR Cloud Benchmarking Guide to learn which network interfaces need to be configured for each guest type. The table looks like this:</p> <table border="1"> <thead> <tr> <th></th> <th>OAM (XMI)</th> <th>Local (IMI)</th> </tr> </thead> <tbody> <tr> <td>Type of guest host</td> <td>eth#</td> <td>eth#</td> </tr> </tbody> </table> <p><b>Note:</b> The VNICs need to be created in the correct order so that the interfaces are associated with the correct network.</p>		OAM (XMI)	Local (IMI)	Type of guest host	eth#	eth#
	OAM (XMI)	Local (IMI)						
Type of guest host	eth#	eth#						
6. <input type="checkbox"/>	<b>OVM-M CLI:</b> Attach XMI VNIC (if required by guest host type)	<p><b>Add (attach) VNIC ID of the XMI network to VM:</b></p> <ol style="list-style-type: none"> <li>Get the site-specific text for these variables (overwrite example)            &lt;VNIC 1 ID&gt; = 0004fb0000070000091e1ab5ae291d8a            &lt;OVM network ID for XMI&gt; = 10345112c9</li> <li>Use the respective values for &lt;VNIC 1 ID&gt; and &lt;OVM network ID for XMI&gt; into the command  <pre>OVM&gt; add Vnic ID=&lt;Vnic 1 ID&gt; to Network name=&lt;OVM network ID for XMI&gt;</pre> <p>Example:  <pre>OVM&gt; add Vnic ID=0004fb0000070000091e1ab5ae291d8a to Network name=10345112c9</pre></p> </li> <li>Execute the command and validate success.  <pre>Command: add Vnic id=0004fb0000070000091e1ab5ae291d8a to Network name=10345112c9 Status: Success Time: 2017-04-19 19:08:59,496 EDT JobId: 1492643339327</pre> </li> </ol>						

**Procedure 4. Configure each SDS VM**

Step	Procedure	Description
7. <input type="checkbox"/>	<b>OVM-M CLI:</b> Create and attach IMI VNIC (if required by guest host type)	<p><b>Create VNIC ID on the IMI network and attach to VM:</b></p> <ol style="list-style-type: none"> <li>Get the site-specific text for these variables (overwrite example).            &lt;VM name&gt; = <code>na-sdsnoam-na-2a</code>            &lt;OVM network ID for IMI&gt; = <code>102e89a481</code></li> <li>Use the respective values for &lt;OVM network ID for IMI&gt; and &lt;VM name&gt; into the command.   <pre>OVM&gt; create Vnic network=&lt;OVM network ID for IMI&gt; name=&lt;VM name&gt;-IMI on Vm name=&lt;VM name&gt;</pre> <p>Example:</p> <pre>OVM&gt; create Vnic network=102e89a481 name=na-sdsnoam-na-2a-IMI on Vm name=na-sdsnoam-na-2a</pre></li> <li>Execute the command and validate success.             Command: <code>create Vnic network=102e89a481 name=na-sdsnoam-na-2a-IMI on Vm name=na-sdsnoam-na-2a</code>            Status: Success            Time: 2017-04-19 21:21:57,363 EDT            JobId: 1492651317194            Data:            id:0004fb00000700004f16dc3bfe0750a7 name:na-sdsnoam-na-2a-IMI</li> </ol>
8. <input type="checkbox"/>	<b>OVM-M CLI:</b> Start VM	<ol style="list-style-type: none"> <li>Get the site-specific text for these variables (overwrite example).            &lt;VM name&gt; = <code>na-sdsnoam-na-2a</code></li> <li>Use the respective values for &lt;VM name&gt; into the command.   <pre>OVM&gt; start Vm name=&lt;VM name&gt;</pre> <p>Example:</p> <pre>OVM&gt; start Vm name=na-sdsnoam-na-2a</pre></li> <li>Execute the command and validate success.             Command: <code>start Vm name=na-sdsnoam-na-2a</code>            Status: Success            Time: 2017-04-19 19:29:35,376 EDT            JobId: 1492644568558</li> </ol>



**Procedure 4. Configure each SDS VM**

Step	Procedure	Description
9. <input type="checkbox"/>	<b>OVM-M GUI:</b> Configure the XMI network interface for this VM	<ol style="list-style-type: none"> <li>1. Get the site-specific text for these variables (overwrite example).            &lt;URL for OVM GUI&gt; =  <a href="https://100.64.62.221:7002/ovm/console/faces/resource/resourceView.jspx">https://100.64.62.221:7002/ovm/console/faces/resource/resourceView.jspx</a>            &lt;interface name&gt; = from the table in [1] DSR Cloud Benchmarking Guide            &lt;VM IP in XMI&gt; = from the NAPD            &lt;Gateway for XMI&gt; = from the NAPD            &lt;NetMask for XMI&gt; = from the NAPD</li> <li>2. Access the CLI of the console for the VM:</li> <li>3. Log into the <b>OVM-M GUI</b> by typing the <b>&lt;URL for OVM GUI&gt;</b> into a browser.           <ol style="list-style-type: none"> <li>a. Navigate to the Servers and VMs tab.</li> <li>a. Expand and select the &lt;ServerPool name&gt;.</li> <li>b. From the <b>Perspective</b> list, select <b>Virtual Machines</b>.</li> <li>c. Select the &lt;VM name&gt; from the rows listed, and click the Launch Console icon.</li> <li>d. In the Console window, log into the VM as the admusr.</li> </ol> </li> <li>4. Use the respective values for &lt;interface name&gt;, &lt;VM IP in XMI&gt;, &lt;Gateway for XMI&gt;, and &lt;NetMask for XMI&gt; into the commands  <b>XMI:</b>  <pre>\$ sudo netAdm set --onboot=yes --device=&lt;interface name&gt; --address=&lt;VM IP in XMI&gt; --netmask=&lt;NetMask for XMI&gt;  \$ sudo netAdm add --route=default --device=&lt;interface name&gt; -gateway=&lt;Gateway for XMI&gt;</pre> <p>Example:</p> <pre>\$ sudo netAdm set --onboot=yes --device=eth0 -- address=10.75.158.189 --netmask=255.255.255.128</pre> <p>Example:</p> <pre>\$ sudo netAdm add --route=default --device=eth0 -- gateway=10.75.158.129</pre> </li> <li>5. Execute the command and validate success</li> <li>6. Verify network connectivity by pinging Gateway of network  <pre>\$ ping -c3 &lt;Gateway for XMI&gt;</pre> </li> <li>7. Reboot the VM. It takes approximately 5 minutes for the VM to complete booting.  <pre>\$ sudo init 6</pre> </li> </ol> <p>The new VM should now be accessible using both network and console.</p>

### 3. Configuration Procedures


#### 3.1 Configure SDS NOAM Servers (1<sup>st</sup> Site Only)

Assumptions:




- This procedure assumes the SDS Network Element XML file for the Primary Provisioning SDS site has previously been created as described in Appendix A Create an XML file for Installing SDS Network Elements.
- This procedure assumes the Network Element XML files are on the laptop's hard drive.

This procedure requires the user to connect to the SDS GUI before configuring the first SDS server.



##### Procedure 5. Configure SDS Servers A and B (1<sup>st</sup> SDS NOAM Site only)

Step	Procedure	Description
1. <input type="checkbox"/>	<b>SDS NOAM-A:</b> Launch an approved web browser and connect to the SDS NOAM-A XMI IP address	If the Security Certificate Warning screen displays, click <b>Continue to this website (not recommended)</b> . 

**Procedure 5. Configure SDS Servers A and B (1<sup>st</sup> SDS NOAM Site only)**

Step	Procedure	Description
<p>2. <input type="checkbox"/></p>	<p><b>SDS NOAM-A: Login</b></p>	<p>Establish a GUI session as the <b>guiadmin</b> user on the NOAM-A server by using the XMI IP address.</p>  <p>Welcome to the Oracle System Login.</p> <p>This application is designed to work with most modern HTML5 compliant browsers and uses both JavaScript and cookies. Please refer to the <a href="#">Oracle Software Web Browser Support Policy</a> for details.</p> <p>Unauthorized access is prohibited.</p> <p><i>Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.</i></p> <p><i>Copyright © 2010, 2017, Oracle and/or its affiliates. All rights reserved.</i></p>
<p>3. <input type="checkbox"/></p>	<p><b>SDS NOAM-A: Create the SDS NOAM-A network element using the XML file</b></p>	<p>1. Navigate to <b>Configuration &gt; Networking &gt; Networks</b>.</p>  <p>Click <b>Browse</b> and type the pathname of the NOAM network XML file.</p>  <p><b>Note:</b> This step assumes the <b>XML</b> files were previously prepared as described in Appendix A Create an XML file for Installing SDS Network Elements.</p>


**Procedure 5. Configure SDS Servers A and B (1<sup>st</sup> SDS NOAM Site only)**

Step	Procedure	Description																								
		<p>2. Select the location of the <b>XML</b> file and click <b>Open</b>.</p>  <p>3. Click <b>Upload File</b> to upload the XML file.</p> <p>To create a new Network Element, upload a valid configuration file:</p> <p><input type="button" value="Browse..."/> zombie.xml <input type="button" value="Upload File"/></p> <p>If the values in the <b>XML</b> file pass, an information banner displays.</p> <p><b>Main Menu: Configuration -&gt; Networking -&gt; Networks</b></p>  <p><b>Note:</b> You may need to left-click on the Info banner to display the banner.</p>																								
<p>4.</p> <p><input type="checkbox"/></p>	<p><b>SDS NOAM-A:</b> Map services to networks</p>	<p>1. Navigate to <b>Configuration &gt; Networking &gt; Services</b>.</p> <p>2. Click <b>Edit</b>.</p> <p><b>Main Menu: Configuration -&gt; Networking -&gt; Services</b></p> <table border="1" data-bbox="553 1591 1433 1812"> <thead> <tr> <th>Name</th> <th>Intra-NE Network</th> <th>Inter-NE Network</th> </tr> </thead> <tbody> <tr> <td>OAM</td> <td>Unspecified</td> <td>INTERNALXMI</td> </tr> <tr> <td>Replication</td> <td>Unspecified</td> <td>INTERNALXMI</td> </tr> <tr> <td>Signaling</td> <td>Unspecified</td> <td>INTERNALXMI</td> </tr> <tr> <td>HA_Secondary</td> <td>Unspecified</td> <td>INTERNALXMI</td> </tr> <tr> <td>HA_MP_Secondary</td> <td>Unspecified</td> <td>INTERNALXMI</td> </tr> <tr> <td>Replication_MP</td> <td>Unspecified</td> <td>INTERNALXMI</td> </tr> <tr> <td>ComAgent</td> <td>Unspecified</td> <td>INTERNALXMI</td> </tr> </tbody> </table> <p>3. Set the services as shown in the table below:</p>	Name	Intra-NE Network	Inter-NE Network	OAM	Unspecified	INTERNALXMI	Replication	Unspecified	INTERNALXMI	Signaling	Unspecified	INTERNALXMI	HA_Secondary	Unspecified	INTERNALXMI	HA_MP_Secondary	Unspecified	INTERNALXMI	Replication_MP	Unspecified	INTERNALXMI	ComAgent	Unspecified	INTERNALXMI
Name	Intra-NE Network	Inter-NE Network																								
OAM	Unspecified	INTERNALXMI																								
Replication	Unspecified	INTERNALXMI																								
Signaling	Unspecified	INTERNALXMI																								
HA_Secondary	Unspecified	INTERNALXMI																								
HA_MP_Secondary	Unspecified	INTERNALXMI																								
Replication_MP	Unspecified	INTERNALXMI																								
ComAgent	Unspecified	INTERNALXMI																								


**Procedure 5. Configure SDS Servers A and B (1<sup>st</sup> SDS NOAM Site only)**

Step	Procedure	Description																								
		<table border="1"> <thead> <tr> <th data-bbox="553 300 854 338">Name</th> <th data-bbox="854 300 1154 338">Intra-NE Network</th> <th data-bbox="1154 300 1448 338">Inter-NE Network</th> </tr> </thead> <tbody> <tr> <td data-bbox="553 338 854 384">OAM</td> <td data-bbox="854 338 1154 384">&lt;IMI Network&gt;</td> <td data-bbox="1154 338 1448 384">&lt;XMI Network&gt;</td> </tr> <tr> <td data-bbox="553 384 854 430">Replication</td> <td data-bbox="854 384 1154 430">&lt;IMI Network&gt;</td> <td data-bbox="1154 384 1448 430">&lt;XMI Network&gt;</td> </tr> <tr> <td data-bbox="553 430 854 476">Signaling</td> <td data-bbox="854 430 1154 476">Unspecified</td> <td data-bbox="1154 430 1448 476">&lt;XMI Network&gt;</td> </tr> <tr> <td data-bbox="553 476 854 522">HA_Secondary</td> <td data-bbox="854 476 1154 522">&lt;IMI Network&gt;</td> <td data-bbox="1154 476 1448 522">&lt;XMI Network&gt;</td> </tr> <tr> <td data-bbox="553 522 854 569">HA_MP_Secondary</td> <td data-bbox="854 522 1154 569">&lt;IMI Network&gt;</td> <td data-bbox="1154 522 1448 569">&lt;XMI Network&gt;</td> </tr> <tr> <td data-bbox="553 569 854 615">Replication_MP</td> <td data-bbox="854 569 1154 615">&lt;IMI Network&gt;</td> <td data-bbox="1154 569 1448 615">&lt;XMI Network&gt;</td> </tr> <tr> <td data-bbox="553 615 854 661">ComAgent</td> <td data-bbox="854 615 1154 661">&lt;IMI Network&gt;</td> <td data-bbox="1154 615 1448 661">&lt;XMI Network&gt;</td> </tr> </tbody> </table>	Name	Intra-NE Network	Inter-NE Network	OAM	<IMI Network>	<XMI Network>	Replication	<IMI Network>	<XMI Network>	Signaling	Unspecified	<XMI Network>	HA_Secondary	<IMI Network>	<XMI Network>	HA_MP_Secondary	<IMI Network>	<XMI Network>	Replication_MP	<IMI Network>	<XMI Network>	ComAgent	<IMI Network>	<XMI Network>
Name	Intra-NE Network	Inter-NE Network																								
OAM	<IMI Network>	<XMI Network>																								
Replication	<IMI Network>	<XMI Network>																								
Signaling	Unspecified	<XMI Network>																								
HA_Secondary	<IMI Network>	<XMI Network>																								
HA_MP_Secondary	<IMI Network>	<XMI Network>																								
Replication_MP	<IMI Network>	<XMI Network>																								
ComAgent	<IMI Network>	<XMI Network>																								
		<p data-bbox="553 688 1430 747">For example, if your IMI network is named <b>IMI</b> and your XMI network is named <b>XMI</b>, then your services configuration should look like the following:</p> <table border="1" data-bbox="553 768 1308 1520"> <thead> <tr> <th data-bbox="561 779 789 816">Name</th> <th data-bbox="789 779 1049 816">Intra-NE Network</th> <th data-bbox="1049 779 1300 816">Inter-NE Network</th> </tr> </thead> <tbody> <tr> <td data-bbox="561 816 789 936">OAM</td> <td data-bbox="789 816 1049 936">INTERNALIMI ▼</td> <td data-bbox="1049 816 1300 936">INTERNALXMI ▼</td> </tr> <tr> <td data-bbox="561 936 789 1035">Replication</td> <td data-bbox="789 936 1049 1035">INTERNALIMI ▼</td> <td data-bbox="1049 936 1300 1035">INTERNALXMI ▼</td> </tr> <tr> <td data-bbox="561 1035 789 1134">Signaling</td> <td data-bbox="789 1035 1049 1134">Unspecified ▼</td> <td data-bbox="1049 1035 1300 1134">INTERNALXMI ▼</td> </tr> <tr> <td data-bbox="561 1134 789 1232">HA_Secondary</td> <td data-bbox="789 1134 1049 1232">INTERNALIMI ▼</td> <td data-bbox="1049 1134 1300 1232">INTERNALXMI ▼</td> </tr> <tr> <td data-bbox="561 1232 789 1331">HA_MP_Secondary</td> <td data-bbox="789 1232 1049 1331">INTERNALIMI ▼</td> <td data-bbox="1049 1232 1300 1331">INTERNALXMI ▼</td> </tr> <tr> <td data-bbox="561 1331 789 1430">Replication_MP</td> <td data-bbox="789 1331 1049 1430">INTERNALIMI ▼</td> <td data-bbox="1049 1331 1300 1430">INTERNALXMI ▼</td> </tr> <tr> <td data-bbox="561 1430 789 1520">ComAgent</td> <td data-bbox="789 1430 1049 1520">INTERNALIMI ▼</td> <td data-bbox="1049 1430 1300 1520">INTERNALXMI ▼</td> </tr> </tbody> </table> <div data-bbox="561 1528 891 1598" style="text-align: center;"> <input type="button" value="Ok"/> <input type="button" value="Apply"/> <input type="button" value="Cancel"/> </div> <p data-bbox="553 1629 1377 1688">4. Click <b>OK</b> to apply the Service-to-Network selections. Dismiss any possible popup notifications.</p>	Name	Intra-NE Network	Inter-NE Network	OAM	INTERNALIMI ▼	INTERNALXMI ▼	Replication	INTERNALIMI ▼	INTERNALXMI ▼	Signaling	Unspecified ▼	INTERNALXMI ▼	HA_Secondary	INTERNALIMI ▼	INTERNALXMI ▼	HA_MP_Secondary	INTERNALIMI ▼	INTERNALXMI ▼	Replication_MP	INTERNALIMI ▼	INTERNALXMI ▼	ComAgent	INTERNALIMI ▼	INTERNALXMI ▼
Name	Intra-NE Network	Inter-NE Network																								
OAM	INTERNALIMI ▼	INTERNALXMI ▼																								
Replication	INTERNALIMI ▼	INTERNALXMI ▼																								
Signaling	Unspecified ▼	INTERNALXMI ▼																								
HA_Secondary	INTERNALIMI ▼	INTERNALXMI ▼																								
HA_MP_Secondary	INTERNALIMI ▼	INTERNALXMI ▼																								
Replication_MP	INTERNALIMI ▼	INTERNALXMI ▼																								
ComAgent	INTERNALIMI ▼	INTERNALXMI ▼																								

**Procedure 5. Configure SDS Servers A and B (1<sup>st</sup> SDS NOAM Site only)**

Step	Procedure	Description
		<p>You must restart the applications running on all servers to apply any services changes. TO RESTART: Use "Restart" button under Status &amp; Manage-&gt;Server tab, ComAgent</p>  <p>The image shows a screenshot of a dialog box with a light gray background. It contains two buttons: "OK" and "Cancel". The "OK" button is highlighted with a blue dashed border, indicating it is the active or default button. The "Cancel" button is a standard gray button.</p>

**Procedure 5. Configure SDS Servers A and B (1<sup>st</sup> SDS NOAM Site only)**


Step	Procedure	Description														
<p>5.</p> <p><input type="checkbox"/></p>	<p><b>SDS NOAM-A:</b> Insert the 1st VM</p>	<p>1. Navigate to <b>Configuration &gt; Servers</b>.</p>  <p>2. Click <b>Insert</b> to insert the new NOAM server into servers table (the first or server).</p> <p>3. Fill in the fields as follows:</p> <p><b>Hostname:</b> Assigned Hostname  <b>Role:</b> NETWORK OAM&amp;P  <b>System ID:</b> Assigned Hostname  <b>Hardware Profile:</b> SDS Cloud Guest  <b>Network Element Name:</b> [Select NE from list]  <b>Location:</b> Optional</p> <table border="1" data-bbox="565 987 1295 1726"> <thead> <tr> <th>Attribute</th> <th>Value</th> </tr> </thead> <tbody> <tr> <td>Hostname *</td> <td>SDS-NO1</td> </tr> <tr> <td>Role *</td> <td>NETWORK OAM&amp;P</td> </tr> <tr> <td>System ID</td> <td>SDS-NO1</td> </tr> <tr> <td>Hardware Profile</td> <td>SDS Cloud Guest</td> </tr> <tr> <td>Network Element Name *</td> <td>SDS_OVM_NO_NE</td> </tr> <tr> <td>Location</td> <td>Bangalore</td> </tr> </tbody> </table>	Attribute	Value	Hostname *	SDS-NO1	Role *	NETWORK OAM&P	System ID	SDS-NO1	Hardware Profile	SDS Cloud Guest	Network Element Name *	SDS_OVM_NO_NE	Location	Bangalore
Attribute	Value															
Hostname *	SDS-NO1															
Role *	NETWORK OAM&P															
System ID	SDS-NO1															
Hardware Profile	SDS Cloud Guest															
Network Element Name *	SDS_OVM_NO_NE															
Location	Bangalore															

**Procedure 5. Configure SDS Servers A and B (1<sup>st</sup> SDS NOAM Site only)**

Step	Procedure	Description																							
<p>6.</p> <p><input type="checkbox"/></p>	<p><b>SDS NOAM-A:</b> Insert the 1st VM</p>	<p>The network interface fields are now available with selection choices based on the chosen hardware profile and network element.</p> <div data-bbox="560 380 1437 737" style="border: 1px solid #ccc; padding: 5px;"> <p><b>OAM Interfaces [At least one interface is required.]:</b></p> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 30%;">Network</th> <th style="width: 30%;">IP Address</th> <th style="width: 40%;">Interface</th> </tr> </thead> <tbody> <tr> <td>INTERNALXMI (10.196.227.0/24)</td> <td>10.196.227.33</td> <td>eth0 <input type="checkbox"/> VLAN (6)</td> </tr> <tr> <td>INTERNALIMI (169.254.1.0/24)</td> <td>169.254.1.33</td> <td>eth1 <input type="checkbox"/> VLAN (3)</td> </tr> </tbody> </table> <p><b>NTP Servers:</b></p> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 60%;">NTP Server IP Address</th> <th style="width: 20%;">Prefer</th> <th style="width: 20%;"></th> </tr> </thead> <tbody> <tr> <td>10.240.191.174</td> <td><input checked="" type="checkbox"/></td> <td style="text-align: right;"> <input type="button" value="Add"/>  <input type="button" value="Remove"/> </td> </tr> </tbody> </table> <p style="margin-top: 5px;"> <input type="button" value="Ok"/> <input type="button" value="Apply"/> <input type="button" value="Cancel"/> </p> </div> <ol style="list-style-type: none"> <li>1. Type the server IP addresses for the XMI network. Select <b>ethX</b> for the interface. Leave the <b>VLAN</b> checkbox unchecked.</li> <li>2. Type the server IP addresses for the IMI network. Select <b>ethX</b> for the interface. Leave the <b>VLAN</b> checkbox unchecked.</li> </ol> <p><b>Note:</b> For OpenStack, these IP addresses must be the addresses used during instance booting and networking.</p> <ol style="list-style-type: none"> <li>3. Add the following NTP servers:             <table border="1" style="width: 100%; border-collapse: collapse; margin-top: 10px;"> <thead> <tr> <th style="width: 60%;">NTP Server</th> <th style="width: 40%;">Preferred?</th> </tr> </thead> <tbody> <tr> <td>Valid NTP Server</td> <td>Yes</td> </tr> <tr> <td>Valid NTP Server (Optional)</td> <td>No</td> </tr> <tr> <td>Valid NTP Server (Optional)</td> <td>No</td> </tr> </tbody> </table> </li> <li>4. Optionally, mark the <b>Prefer</b> checkbox to prefer one server over the other.</li> <li>5. Click <b>OK</b> when you have completed entering all the server data.</li> </ol>	Network	IP Address	Interface	INTERNALXMI (10.196.227.0/24)	10.196.227.33	eth0 <input type="checkbox"/> VLAN (6)	INTERNALIMI (169.254.1.0/24)	169.254.1.33	eth1 <input type="checkbox"/> VLAN (3)	NTP Server IP Address	Prefer		10.240.191.174	<input checked="" type="checkbox"/>	<input type="button" value="Add"/> <input type="button" value="Remove"/>	NTP Server	Preferred?	Valid NTP Server	Yes	Valid NTP Server (Optional)	No	Valid NTP Server (Optional)	No
Network	IP Address	Interface																							
INTERNALXMI (10.196.227.0/24)	10.196.227.33	eth0 <input type="checkbox"/> VLAN (6)																							
INTERNALIMI (169.254.1.0/24)	169.254.1.33	eth1 <input type="checkbox"/> VLAN (3)																							
NTP Server IP Address	Prefer																								
10.240.191.174	<input checked="" type="checkbox"/>	<input type="button" value="Add"/> <input type="button" value="Remove"/>																							
NTP Server	Preferred?																								
Valid NTP Server	Yes																								
Valid NTP Server (Optional)	No																								
Valid NTP Server (Optional)	No																								



**Procedure 5. Configure SDS Servers A and B (1<sup>st</sup> SDS NOAM Site only)**

Step	Procedure	Description														
7. <input type="checkbox"/>	<b>SDS NOAM-A:</b> Export the initial configuration	<p>1. Navigate to <b>Configuration &gt; Servers</b>.</p>  <p>2. From the GUI screen, select the SDS server and click <b>Export</b> to generate the initial configuration data for that server. Go to the Info tab to confirm the file has been created.</p> <p><b>Main Menu: Configuration -&gt; Servers</b></p> <p>Filter*</p> <table border="1"> <thead> <tr> <th>Hostname</th> <th>Role</th> <th>System ID</th> <th>Server Group</th> <th>Network Element</th> <th>Location</th> <th>Place</th> </tr> </thead> <tbody> <tr> <td>SDS-N01</td> <td>Network OAM&amp;P</td> <td>SDS-N01</td> <td>NO_S0</td> <td>SDS_OVM_NO_NE</td> <td>Bangalore</td> <td></td> </tr> </tbody> </table> <p>Insert Edit Delete <b>Export</b> Report</p>	Hostname	Role	System ID	Server Group	Network Element	Location	Place	SDS-N01	Network OAM&P	SDS-N01	NO_S0	SDS_OVM_NO_NE	Bangalore	
Hostname	Role	System ID	Server Group	Network Element	Location	Place										
SDS-N01	Network OAM&P	SDS-N01	NO_S0	SDS_OVM_NO_NE	Bangalore											
8. <input type="checkbox"/>	<b>SDS NOAM-A:</b> Copy server configuration file to /var/tmp directory	<p>1. Obtain a terminal window to the SDS NOAM-A server, logging in as the <b>admusr</b> user.</p> <p>2. Copy the configuration file created in the previous step from the <b>/var/TKLC/db/filemgmt</b> directory on the SDS NOAM-A to the <b>/var/tmp</b> directory. The configuration file has a filename like <b>TKLCConfigData.&lt;hostname&gt;.sh</b>. The following is an example:</p> <pre>\$ cp /var/TKLC/db/filemgmt/TKLCConfigData.&lt;NOAM-A_hostname&gt;.sh /var/tmp/TKLCConfigData.sh</pre> <p><b>Note:</b> The server polls the /var/tmp directory for the configuration file and automatically executes it.</p> <p>For the NOAM-B server, the command is:</p> <pre>\$ scp \ /var/TKLC/db/filemgmt/TKLCConfigData.&lt;NOAM-B_hostname&gt;.sh \ &lt;NOAM-B_ipaddr&gt;:/var/tmp/TKLCConfigData.sh</pre> <p><b>Note:</b> The IPADDR is the IP address of NOAM-B associated with the XMI network.</p>														

**Procedure 5. Configure SDS Servers A and B (1<sup>st</sup> SDS NOAM Site only)**

Step	Procedure	Description
9. <input type="checkbox"/>	<b>SDS NOAM-A:</b> Wait for configuration to complete	<p>The automatic configuration daemon looks for the file named <b>TKLCConfigData.sh</b> in the <b>/var/tmp</b> directory, implements the configuration in the file, and prompts the user to reboot the server.</p> <p>A broadcast message is sent to the terminal. This can take anywhere from 3-20 minutes to complete.</p> <p>If you are on the console, wait to be prompted to reboot the server, but <b>DO NOT</b> reboot the server, it is rebooted later in this procedure.</p> <p>Verify the script completed successfully by checking the following file.</p> <pre>\$ sudo cat /var/TKLC/appw/logs/Process/install.log</pre> <p><b>Note:</b> Ignore the warning about removing the USB key since no USB key is present. No response occurs until the reboot prompt is issued.</p>
10. <input type="checkbox"/>	<b>SDS NOAM-A:</b> Set the time zone (Optional) and reboot the server	<ol style="list-style-type: none"> <li>To change the system time zone, from the command line prompt, execute <b>set_ini_tz.pl</b>. The following command example uses the America/New_York time zone.</li> <li>Replace, as appropriate, with the time zone you have selected for this installation. For a full list of valid time zones, see Appendix B List of Frequently Used Time Zones.</li> </ol> <pre>\$ sudo /usr/TKLC/appworks/bin/set_ini_tz.pl "America/New_York" &gt;/dev/null 2&gt;&amp;1 \$ sudo init 6</pre> <ol style="list-style-type: none"> <li>Wait for server to reboot.</li> </ol>
11. <input type="checkbox"/>	<b>SDS NOAM-A:</b> Verify server health	<ol style="list-style-type: none"> <li>Log into the NOAM1 as the <b>admusr</b> user.</li> <li>Execute the following command on the 1<sup>st</sup> NOAM server and make sure no errors are returned:</li> </ol> <pre>\$ sudo syscheck Running modules in class hardware...                                 OK Running modules in class disk...                                 OK Running modules in class net...                                 OK Running modules in class system...                                 OK Running modules in class proc...                                 OK LOG LOCATION: /var/TKLC/log/syscheck/fail_log</pre>
12. <input type="checkbox"/>	<b>SDS NOAM-A:</b> Verify server health	<p>Exit from the command line to return to the server console.</p> <pre>\$ exit sds-mrsvnc-a login:</pre>


**Procedure 5. Configure SDS Servers A and B (1<sup>st</sup> SDS NOAM Site only)**

Step	Procedure	Description
13. <input type="checkbox"/>	<b>SDS NOAM-B:</b> Repeat	Configure DR SDS NOAM-B by repeating steps 5. through 12. of this procedure.


**3.2 OAM Pairing (1st SDS NOAM Site Only)**

During the OAM pairing procedure, various errors may display at different stages of the procedure. During the execution of a step, ignore errors related to values other than the ones referenced by that step.




**Procedure 6. Configure the SDS Server Group**

Step	Procedure	Description
1. <input type="checkbox"/>	<b>SDS NOAM-A:</b> Launch an approved web browser and connect to the SDS NOAM-A using an https:// address	<p>If the Security Certificate Warning screen displays, click <b>Continue to this website (not recommended)</b>.</p> 

**Procedure 6. Configure the SDS Server Group**

Step	Procedure	Description
2. <input type="checkbox"/>	<b>SDS NOAM-A:</b> Login	Establish a GUI session as the <b>guiadmin</b> user on the NOAM-A server.   <p style="text-align: center;">Welcome to the Oracle System Login.</p> <p style="text-align: center;">This application is designed to work with most modern HTML5 compliant browsers and uses both JavaScript and cookies. Please refer to the <a href="#">Oracle Software Web Browser Support Policy</a> for details.</p> <p style="text-align: center;">Unauthorized access is prohibited.</p>




**Procedure 6. Configure the SDS Server Group**

Step	Procedure	Description
<p>3.</p> <p><input type="checkbox"/></p>	<p><b>SDS NOAM-A:</b> Enter group data</p>	<p>1. Navigate to <b>Configuration &gt; Server Groups</b>.</p>  <p>2. Click <b>Insert</b>.</p>  <p>3. Fill in the following fields:</p> <p><b>Server Group Name:</b> [Type Server Group Name]  <b>Level:</b> A  <b>Parent:</b> None  <b>Function:</b> SDS  <b>WAN Replication Connection Count:</b> Use Default Value</p> <p><b>Main Menu: Configuration -&gt; Server Groups [Insert]</b></p>  <p>4. Click <b>OK</b> when all fields are filled in.</p>


**Procedure 6. Configure the SDS Server Group**

Step	Procedure	Description																			
<p>4.</p> <p><input type="checkbox"/></p>	<p><b>SDS NOAM-A:</b> Add server to OAM Server Group</p>	<p>1. Select the new server group and click <b>Edit</b>.</p> <p><b>Main Menu: Configuration -&gt; Server Groups</b></p> <p>Filter* <input type="text"/></p> <table border="1"> <thead> <tr> <th>Server Group Name</th> <th>Level</th> <th>Parent</th> <th>Function</th> <th>Connection Count</th> </tr> </thead> <tbody> <tr> <td>NO_SG</td> <td>A</td> <td>NONE</td> <td>SDS</td> <td>1</td> </tr> </tbody> </table> <p>Insert Edit Delete Report</p> <p>2. In the portion of the screen that lists the servers for the server group, find the SDS-NOAM servers being configured. Mark the <b>Include in SG</b> checkbox.</p> <p>SDS_OVM_NO_NE <input type="checkbox"/> Prefer Network Element as spare</p> <table border="1"> <thead> <tr> <th>Server</th> <th>SG Inclusion</th> <th>Preferred HA Role</th> </tr> </thead> <tbody> <tr> <td>SDS-NO1</td> <td><input checked="" type="checkbox"/> Include in SG</td> <td><input type="checkbox"/> Prefer server as spare</td> </tr> <tr> <td>SDS-NO2</td> <td><input checked="" type="checkbox"/> Include in SG</td> <td><input type="checkbox"/> Prefer server as spare</td> </tr> </tbody> </table> <p>VIP Assignment</p> <p>VIP Address <input type="text"/> Add</p> <p>Ok Apply Cancel</p> <p>3. Leave other boxes unchecked.</p> <p>4. Click <b>Apply</b>.</p>	Server Group Name	Level	Parent	Function	Connection Count	NO_SG	A	NONE	SDS	1	Server	SG Inclusion	Preferred HA Role	SDS-NO1	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare	SDS-NO2	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare
Server Group Name	Level	Parent	Function	Connection Count																	
NO_SG	A	NONE	SDS	1																	
Server	SG Inclusion	Preferred HA Role																			
SDS-NO1	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare																			
SDS-NO2	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare																			

**Procedure 6. Configure the SDS Server Group**



Step	Procedure	Description
<p>5.</p> <p><input type="checkbox"/></p>	<p><b>SDS NOAM-A:</b> Add VIP address</p>	<p>Click <b>Add</b>.</p>  <p>Type the <b>VIP Address</b> and click <b>Apply</b>.</p>  <p>This process takes a minimum of 5 minutes, depending on the underlying infrastructure. The server pairs within the server group and establishes a master/slave relationship for High Availability (HA).</p>
<p>6.</p> <p><input type="checkbox"/></p>	<p><b>SDS VIP:</b> Launch an approved web browser and connect to the XMI virtual IP address assigned in step 5 to the SDS server group using https://.</p>	<p>If the Security Certificate Warning screen displays, click <b>Continue to this website (not recommended)</b>.</p> 

**Procedure 6. Configure the SDS Server Group**

Step	Procedure	Description
<p>7.</p> <p><input type="checkbox"/></p>	<p><b>SDS VIP: Login</b></p>	<p>Establish a GUI session as the <b>guiadmin</b> user on the NOAM-A server by using the XMI IP address.</p> <div style="text-align: center;">  <p><b>ORACLE®</b></p> <p><b>Oracle System Login</b> <span style="float: right;">Mon Jul 11 13:59:37 2016 EDT</span></p> <div style="border: 1px solid #ccc; padding: 10px; width: fit-content; margin: 10px auto;"> <p style="text-align: center;"><b>Log In</b></p> <p style="text-align: center;">Enter your username and password to log in</p> <p>Username: <input type="text"/></p> <p>Password: <input type="password"/></p> <p style="text-align: center;"><input type="checkbox"/> Change password</p> <p style="text-align: center;"><input type="button" value="Log In"/></p> </div> <p style="text-align: center;">Welcome to the Oracle System Login.</p> <p style="text-align: center;">This application is designed to work with most modern HTML5 compliant browsers and uses both JavaScript and cookies. Please refer to the <a href="#">Oracle Software Web Browser Support Policy</a> for details.</p> <p style="text-align: center;">Unauthorized access is prohibited.</p> </div>




**Procedure 6. Configure the SDS Server Group**

Step	Procedure	Description																																										
<p>8.</p> <p><input type="checkbox"/></p>	<p><b>SDS VIP:</b> Verify and restart the servers</p>	<p>1. Navigate to <b>Status &amp; Manage &gt; Server</b>.</p>  <p>2. Verify the DB status is <b>Norm</b> and the Proc status is <b>Man</b>.</p> <p><b>Main Menu: Status &amp; Manage -&gt; Server</b></p> <p>Filter* <input type="text"/></p> <table border="1" data-bbox="560 850 1437 934"> <thead> <tr> <th>Server Hostname</th> <th>Network Element</th> <th>Appl State</th> <th>Alm</th> <th>DB</th> <th>Reporting Status</th> <th>Proc</th> </tr> </thead> <tbody> <tr> <td>SDS-NO1</td> <td>SDS_OVM_NO_NE</td> <td>Disabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Man</td> </tr> <tr> <td>SDS-NO2</td> <td>SDS_OVM_NO_NE</td> <td>Disabled</td> <td>Warn</td> <td>Norm</td> <td>Norm</td> <td>Man</td> </tr> </tbody> </table> <p>Stop Restart Reboot NTP Sync Report</p> <p>3. Select the SDS NOAM-A server and click <b>Restart</b>.</p> <p>4. Click <b>OK</b> on the confirmation screen.</p> <p>A confirmation banner displays.</p> <p><b>Main Menu: Status &amp; Manage -&gt; Server</b></p> <p>Filter* <input type="text"/> Info <input type="text"/></p>  <p>5. Verify the Appl state is <b>Enabled</b> and the DB and Reporting Status is <b>Norm</b>.</p> <p><b>Main Menu: Status &amp; Manage -&gt; Server</b></p> <p>Filter* <input type="text"/> <span style="float: right;">Tue Jun 21 11:12</span></p> <table border="1" data-bbox="560 1627 1437 1701"> <thead> <tr> <th>Server Hostname</th> <th>Network Element</th> <th>Appl State</th> <th>Alm</th> <th>DB</th> <th>Reporting Status</th> <th>Proc</th> </tr> </thead> <tbody> <tr> <td>SDS-NO1</td> <td>SDS_OVM_NO_NE</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-NO2</td> <td>SDS_OVM_NO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> </tbody> </table> <p><b>Note:</b> To refresh the server status screen before the 15-30 second default, navigate to the <b>Status &amp; Manage &gt; Server</b> screen again.</p>	Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc	SDS-NO1	SDS_OVM_NO_NE	Disabled	Err	Norm	Norm	Man	SDS-NO2	SDS_OVM_NO_NE	Disabled	Warn	Norm	Norm	Man	Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc	SDS-NO1	SDS_OVM_NO_NE	Enabled	Err	Norm	Norm	Norm	SDS-NO2	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm
Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc																																						
SDS-NO1	SDS_OVM_NO_NE	Disabled	Err	Norm	Norm	Man																																						
SDS-NO2	SDS_OVM_NO_NE	Disabled	Warn	Norm	Norm	Man																																						
Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc																																						
SDS-NO1	SDS_OVM_NO_NE	Enabled	Err	Norm	Norm	Norm																																						
SDS-NO2	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm																																						




**Procedure 6. Configure the SDS Server Group**

Step	Procedure	Description
9. <input type="checkbox"/>	<b>SDS NOAM-B:</b> Repeat	Configure SDS NOAM-B by repeating step 8 of this procedure.  This process takes a minimum of 5 minutes, depending on the underlying infrastructure. The server pairs within the server group and establishes a master/slave relationship for High Availability (HA).

**Procedure 7. Verify SDS Server Alarm Status**

Step	Procedure	Description																								
1. <input type="checkbox"/>	<b>SDS VIP:</b> Establish GUI session on the NOAM VIP	<p>Establish a GUI session on the NOAM by using the NOAM VIP address. Login as the <b>guiadmin</b> user.</p>  <p>Welcome to the Oracle System Login.</p> <p>This application is designed to work with most modern HTML5 compliant browsers and uses both JavaScript and cookies. Please refer to the <a href="#">Oracle Software Web Browser Support Policy</a> for details.</p> <p>Unauthorized access is prohibited.</p>																								
2. <input type="checkbox"/>	<b>SDS VIP:</b> Wait for remote database alarm to clear	<p>1. Navigate to <b>Alarms &amp; Events &gt; View Active</b>.</p> <p>2. Verify Event ID <b>14101</b> (No Remote Connections) is the only alarm present on the system at this time.</p> <p><b>Main Menu: Alarms &amp; Events -&gt; View Active (Filtered)</b></p> <p>Filter* Tasks Graph*</p> <p>NO_SG SO_SG</p> <table border="1"> <thead> <tr> <th>Seq #</th> <th>Event ID</th> <th>Timestamp</th> <th>Severity</th> <th>Product</th> <th>Process</th> <th>NE</th> <th>Server</th> </tr> </thead> <tbody> <tr> <td>83</td> <td>14101</td> <td>2016-06-20 13:29:49.058 EDT</td> <td>MAJOR</td> <td>SDS</td> <td>xds</td> <td>SDS_OVM_NO_NE</td> <td>SDS-NO1</td> </tr> <tr> <td></td> <td colspan="2">No Remote Connections</td> <td colspan="5">GN_INFORMWRN for information only [Listener:C:453] ** No XML client connect... <a href="#">More...</a></td> </tr> </tbody> </table>	Seq #	Event ID	Timestamp	Severity	Product	Process	NE	Server	83	14101	2016-06-20 13:29:49.058 EDT	MAJOR	SDS	xds	SDS_OVM_NO_NE	SDS-NO1		No Remote Connections		GN_INFORMWRN for information only [Listener:C:453] ** No XML client connect... <a href="#">More...</a>				
Seq #	Event ID	Timestamp	Severity	Product	Process	NE	Server																			
83	14101	2016-06-20 13:29:49.058 EDT	MAJOR	SDS	xds	SDS_OVM_NO_NE	SDS-NO1																			
	No Remote Connections		GN_INFORMWRN for information only [Listener:C:453] ** No XML client connect... <a href="#">More...</a>																							



**Procedure 8. Configure SNMP for Traps from Individual Servers**

Step	Procedure	Description
1. <input type="checkbox"/>	<b>SDS VIP:</b> Establish GUI session on the NOAM VIP	If needed, establish a GUI session on the NOAM by using the NOAM VIP address. Login as the <b>guiadmin</b> user.
2. <input type="checkbox"/>	<b>SDS VIP:</b> Navigate to SNMP Trapping screen	<p>1. Navigate to <b>Administration &gt; Remote Servers &gt; SNMP Trapping</b>.</p>  <p>2. Click <b>Insert</b>.</p> <p>3. Change the Enabled Versions to <b>SNMPv2c</b>.</p>  <p>4. Mark the Traps from Individual Servers checkbox as <b>Enabled</b>.</p>  <p>5. Click <b>OK</b>.</p>


### 3.3 Query Server Installation (All SDS NOAM Sites)

During the Query Server installation procedure, various errors may display at different stages of the procedure. During the execution of a step, ignore errors related to values other than the ones referenced by that step.

#### Procedure 9. Configure Query Server (All SDS NOAM Sites)

Step	Procedure	Description
<p>1. <input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Launch a web browser.</p>	<p>Connect to the XMI virtual IP address assigned to active SDS site using <b>https://</b>.</p> <p>If the Security Certificate Warning screen displays, click <b>Continue to this website (not recommended)</b>.</p> 
<p>2. <input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Login</p>	<p>Establish a GUI session as the <b>default</b> user.</p> 

**Procedure 9. Configure Query Server (All SDS NOAM Sites)**

Step	Procedure	Description														
<p>3.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Configure Query server</p>	<p>1. Navigate to <b>Configuration &gt; Servers</b>.</p>  <p>2. Click <b>Insert</b> to insert the new NOAM server into servers table (the first or server).</p> <p>3. Fill in the fields as follows:</p> <p><b>Hostname:</b> Assigned Hostname  <b>Role:</b> <a href="#">Query Server</a>  <b>System ID:</b> Leave Blank  <b>Hardware Profile:</b> <a href="#">SDS Cloud Guest</a>  <b>Network Element Name:</b> [Select <b>NE</b> from list where Query server is physically located]  <b>Location:</b> Optional</p> <table border="1" data-bbox="527 1094 1286 1730"> <thead> <tr> <th>Attribute</th> <th>Value</th> </tr> </thead> <tbody> <tr> <td>Hostname *</td> <td>SDS-QS1</td> </tr> <tr> <td>Role *</td> <td>QUERY SERVER</td> </tr> <tr> <td>System ID</td> <td></td> </tr> <tr> <td>Hardware Profile</td> <td>SDS Cloud Guest</td> </tr> <tr> <td>Network Element Name *</td> <td>SDS_OVM_NO_NE</td> </tr> <tr> <td>Location</td> <td>Bangalore</td> </tr> </tbody> </table>	Attribute	Value	Hostname *	SDS-QS1	Role *	QUERY SERVER	System ID		Hardware Profile	SDS Cloud Guest	Network Element Name *	SDS_OVM_NO_NE	Location	Bangalore
Attribute	Value															
Hostname *	SDS-QS1															
Role *	QUERY SERVER															
System ID																
Hardware Profile	SDS Cloud Guest															
Network Element Name *	SDS_OVM_NO_NE															
Location	Bangalore															

**Procedure 9. Configure Query Server (All SDS NOAM Sites)**

Step	Procedure	Description																												
<p>4.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Insert the Query server</p>	<p>The network interface fields are now available with selection choices based on the chosen hardware profile and network element.</p> <div data-bbox="521 386 1427 758" style="border: 1px solid gray; padding: 5px;"> <p><b>OAM Interfaces [At least one interface is required.]:</b></p> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 30%;">Network</th> <th style="width: 30%;">IP Address</th> <th style="width: 40%;">Interface</th> </tr> </thead> <tbody> <tr> <td>INTERNALXMI (10.196.227.0/24)</td> <td>10.196.227.40</td> <td>eth0 <input type="checkbox"/> VLAN (6)</td> </tr> <tr> <td>INTERNALIMI (169.254.1.0/24)</td> <td>169.254.1.40</td> <td>eth1 <input type="checkbox"/> VLAN (3)</td> </tr> </tbody> </table> <p><b>NTP Servers:</b></p> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 50%;">NTP Server IP Address</th> <th style="width: 20%;">Prefer</th> <th style="width: 30%;"></th> </tr> </thead> <tbody> <tr> <td>10.240.191.174</td> <td><input type="checkbox"/></td> <td style="text-align: right;"> <input type="button" value="Add"/> <input type="button" value="Remove"/> </td> </tr> </tbody> </table> <p style="text-align: left;"> <input type="button" value="Ok"/> <input type="button" value="Apply"/> <input type="button" value="Cancel"/> </p> </div> <ol style="list-style-type: none"> <li>1. Type the server IP addresses for the XMI network. Select <b>ethX</b> for the interface. Leave the <b>VLAN</b> checkbox unchecked.</li> <li>2. Type the server IP addresses for the IMI network. Select <b>ethX</b> for the interface. Leave the <b>VLAN</b> checkbox unchecked.</li> </ol> <p><b>Note:</b> For OpenStack, these IP addresses must be the addresses used during instance booting and networking.</p> <ol style="list-style-type: none"> <li>3. Add the following NTP servers:</li> </ol> <table border="1" style="width: 100%; border-collapse: collapse; margin: 10px 0;"> <thead> <tr> <th style="width: 60%;">NTP Server</th> <th style="width: 40%;">Preferred?</th> </tr> </thead> <tbody> <tr> <td>Valid NTP Server</td> <td>Yes</td> </tr> <tr> <td>Valid NTP Server (Optional)</td> <td>No</td> </tr> <tr> <td>Valid NTP Server (Optional)</td> <td>No</td> </tr> </tbody> </table> <ol style="list-style-type: none"> <li>4. Optionally, mark the <b>Prefer</b> checkbox to prefer one server over the other.</li> <li>5. Click <b>OK</b> when you have completed entering all the server data.</li> </ol>	Network	IP Address	Interface	INTERNALXMI (10.196.227.0/24)	10.196.227.40	eth0 <input type="checkbox"/> VLAN (6)	INTERNALIMI (169.254.1.0/24)	169.254.1.40	eth1 <input type="checkbox"/> VLAN (3)	NTP Server IP Address	Prefer		10.240.191.174	<input type="checkbox"/>	<input type="button" value="Add"/> <input type="button" value="Remove"/>	NTP Server	Preferred?	Valid NTP Server	Yes	Valid NTP Server (Optional)	No	Valid NTP Server (Optional)	No					
Network	IP Address	Interface																												
INTERNALXMI (10.196.227.0/24)	10.196.227.40	eth0 <input type="checkbox"/> VLAN (6)																												
INTERNALIMI (169.254.1.0/24)	169.254.1.40	eth1 <input type="checkbox"/> VLAN (3)																												
NTP Server IP Address	Prefer																													
10.240.191.174	<input type="checkbox"/>	<input type="button" value="Add"/> <input type="button" value="Remove"/>																												
NTP Server	Preferred?																													
Valid NTP Server	Yes																													
Valid NTP Server (Optional)	No																													
Valid NTP Server (Optional)	No																													
<p>5.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Export the initial configuration</p>	<p>From the GUI screen, select the SDS server and click <b>Export</b> to generate the initial configuration data for that server. Go to the Info tab to confirm the file has been created.</p> <div data-bbox="521 1478 1427 1780" style="border: 1px solid gray; padding: 5px;"> <p><b>Main Menu: Configuration -&gt; Servers</b></p> <p>Filter* ▾</p> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 15%;">Hostname</th> <th style="width: 15%;">Role</th> <th style="width: 15%;">System ID</th> <th style="width: 15%;">Server Group</th> <th style="width: 15%;">Network Element</th> <th style="width: 15%;">Location</th> <th style="width: 10%;">Place</th> </tr> </thead> <tbody> <tr> <td>SDS-NO1</td> <td>Network OAM&amp;P</td> <td>SDS-NO1</td> <td>NO_80</td> <td>SDS_OVM_NO_NE</td> <td>Bangalore</td> <td></td> </tr> <tr> <td>SDS-NO2</td> <td>Network OAM&amp;P</td> <td>SDS-NO2</td> <td>NO_80</td> <td>SDS_OVM_NO_NE</td> <td>Bangalore</td> <td></td> </tr> <tr style="background-color: #e0f0ff;"> <td>SDS-QS1</td> <td>Query Server</td> <td></td> <td></td> <td>SDS_OVM_NO_NE</td> <td>Bangalore</td> <td></td> </tr> </tbody> </table> <p style="text-align: center; margin-top: 10px;"> <input type="button" value="Insert"/> <input type="button" value="Edit"/> <input type="button" value="Delete"/> <input style="color: blue;" type="button" value="Export"/> <input type="button" value="Report"/> </p> </div>	Hostname	Role	System ID	Server Group	Network Element	Location	Place	SDS-NO1	Network OAM&P	SDS-NO1	NO_80	SDS_OVM_NO_NE	Bangalore		SDS-NO2	Network OAM&P	SDS-NO2	NO_80	SDS_OVM_NO_NE	Bangalore		SDS-QS1	Query Server			SDS_OVM_NO_NE	Bangalore	
Hostname	Role	System ID	Server Group	Network Element	Location	Place																								
SDS-NO1	Network OAM&P	SDS-NO1	NO_80	SDS_OVM_NO_NE	Bangalore																									
SDS-NO2	Network OAM&P	SDS-NO2	NO_80	SDS_OVM_NO_NE	Bangalore																									
SDS-QS1	Query Server			SDS_OVM_NO_NE	Bangalore																									

**Procedure 9. Configure Query Server (All SDS NOAM Sites)**


Step	Procedure	Description
6. <input type="checkbox"/>	<b>Active SDS VIP:</b> Copy server configuration file to /var/tmp directory	<ol style="list-style-type: none"> <li>1. Obtain a terminal window to the active SDS VIP server, logging in as the <b>admusr</b> user.</li> <li>2. Copy the configuration file created in the previous step from the <b>/var/TKLC/db/filemgmt</b> directory on the active SDS VIP to the <b>/var/tmp</b> directory. The configuration file has a filename like <b>TKLCConfigData.&lt;hostname&gt;.sh</b>. The following is an example: <pre>\$ cp /var/TKLC/db/filemgmt/TKLCConfigData.&lt;hostname&gt;.sh /var/tmp/TKLCConfigData.sh</pre> </li> </ol> <p><b>Note:</b> The server polls the /var/tmp directory for the configuration file and automatically executes it.</p> <p>For the NOAM-B server, the command is:</p> <pre>\$ scp \ /var/TKLC/db/filemgmt/TKLCConfigData.&lt;hostname&gt;.sh \ &lt;ipaddr&gt;:/var/tmp/TKLCConfigData.sh</pre> <p><b>Note:</b> The IPADDR is the IP address of the Query server associated with the XMI network.</p>
7. <input type="checkbox"/>	<b>Active SDS VIP:</b> Wait for configuration to complete	<p>The automatic configuration daemon looks for the file named <b>TKLCConfigData.sh</b> in the <b>/var/tmp</b> directory, implements the configuration in the file, and prompts the user to reboot the server.</p> <p>A broadcast message is sent to the terminal. This can take anywhere from 3-20 minutes to complete.</p> <p>If you are on the console, wait to be prompted to reboot the server, but <b>DO NOT</b> reboot the server, it is rebooted later in this procedure.</p> <p>Verify the script completed successfully by checking the following file.</p> <pre>\$ cat /var/TKLC/appw/logs/Process/install.log</pre> <p><b>Note:</b> Ignore the warning about removing the USB key since no USB key is present. No response occurs until the reboot prompt is issued.</p>
8. <input type="checkbox"/>	<b>Active SDS VIP:</b> Set the time zone (Optional) and reboot the server	<ol style="list-style-type: none"> <li>1. To change the system time zone, from the command line prompt, execute <b>set_ini_tz.pl</b>. The following command example uses the America/New_York time zone.</li> <li>2. Replace, as appropriate, with the time zone you have selected for this installation. For a full list of valid time zones, see Appendix B List of Frequently Used Time Zones. <pre>\$ sudo /usr/TKLC/appworks/bin/set_ini_tz.pl "America/New_York" &gt;/dev/null 2&gt;&amp;1</pre> <pre>\$ sudo init 6</pre> </li> <li>3. Wait for server to reboot.</li> </ol>

**Procedure 9. Configure Query Server (All SDS NOAM Sites)**




Step	Procedure	Description
9. <input type="checkbox"/>	<b>Active SDS VIP:</b> Verify server health	<ol style="list-style-type: none"> <li data-bbox="513 300 1055 331">1. Log into the NOAM1 as the <b>admusr</b> user.</li> <li data-bbox="513 342 1409 411">2. Execute the following command on the 1<sup>st</sup> NOAM server and make sure no errors are returned: <pre data-bbox="565 422 1284 873"> \$ sudo syscheck Running modules in class hardware...                                 OK Running modules in class disk...                                 OK Running modules in class net...                                 OK Running modules in class system...                                 OK Running modules in class proc...                                 OK LOG LOCATION: /var/TKLC/log/syscheck/fail_log </pre> </li> </ol>




**Procedure 10. Add Query Server to the SDS Server Group**

Step	Procedure	Description										
<p>1.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Add server to OAM Server Group</p>	<p>1. Navigate to <b>Configuration &gt; Server Groups</b>.</p>  <p>2. Select the new server group and click <b>Edit</b>.</p> <p><b>Main Menu: Configuration -&gt; Server Groups</b></p> <p>Filter* <input type="text"/></p> <table border="1" data-bbox="527 835 1437 987"> <thead> <tr> <th>Server Group Name</th> <th>Level</th> <th>Parent</th> <th>Function</th> <th>Connection Count</th> </tr> </thead> <tbody> <tr> <td>NO_SG</td> <td>A</td> <td>NONE</td> <td>SDS</td> <td>1</td> </tr> </tbody> </table> <p><input type="button" value="Insert"/> <input type="button" value="Edit"/> <input type="button" value="Delete"/> <input type="button" value="Report"/></p> <p>3. In the portion of the screen that lists the servers for the server group, find the Query server being configured. Mark the <b>Include in SG</b> checkbox.</p> <p>SDS-QS1 <input checked="" type="checkbox"/> Include in SG <input type="checkbox"/> Prefer server as spare</p> <p><b>VIP Assignment</b></p> <p>VIP Address <input type="button" value="Add"/></p> <p>10.196.227.41 <input type="button" value="Remove"/></p> <p><input type="button" value="Ok"/> <input type="button" value="Apply"/> <input type="button" value="Cancel"/></p> <p>4. Leave other boxes unchecked.</p> <p>5. Click <b>OK</b>.</p>	Server Group Name	Level	Parent	Function	Connection Count	NO_SG	A	NONE	SDS	1
Server Group Name	Level	Parent	Function	Connection Count								
NO_SG	A	NONE	SDS	1								

**Procedure 10. Add Query Server to the SDS Server Group**

Step	Procedure	Description																								
<p>2.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Wait for process to complete</p>	<table border="1" data-bbox="516 306 1433 422"> <thead> <tr> <th>Server Group Name</th> <th>Level</th> <th>Parent</th> <th>Function</th> <th>Connection Count</th> <th>Servers</th> </tr> </thead> <tbody> <tr> <td>NO_SQ</td> <td>A</td> <td>NONE</td> <td>SDS</td> <td>1</td> <td> <table border="1"> <thead> <tr> <th>Server</th> <th>Node HA Pref</th> <th>VIPs</th> </tr> </thead> <tbody> <tr> <td>SDS-NO1</td> <td></td> <td>10.196.227.41</td> </tr> <tr> <td>SDS-NO2</td> <td></td> <td>10.196.227.41</td> </tr> <tr> <td>SDS-QS1</td> <td></td> <td>10.196.227.41</td> </tr> </tbody> </table> </td> </tr> </tbody> </table> <p>This process takes a minimum of 5 minutes, depending on the underlying infrastructure. The server establishes DB replication with the active SDS server.</p>	Server Group Name	Level	Parent	Function	Connection Count	Servers	NO_SQ	A	NONE	SDS	1	<table border="1"> <thead> <tr> <th>Server</th> <th>Node HA Pref</th> <th>VIPs</th> </tr> </thead> <tbody> <tr> <td>SDS-NO1</td> <td></td> <td>10.196.227.41</td> </tr> <tr> <td>SDS-NO2</td> <td></td> <td>10.196.227.41</td> </tr> <tr> <td>SDS-QS1</td> <td></td> <td>10.196.227.41</td> </tr> </tbody> </table>	Server	Node HA Pref	VIPs	SDS-NO1		10.196.227.41	SDS-NO2		10.196.227.41	SDS-QS1		10.196.227.41
Server Group Name	Level	Parent	Function	Connection Count	Servers																					
NO_SQ	A	NONE	SDS	1	<table border="1"> <thead> <tr> <th>Server</th> <th>Node HA Pref</th> <th>VIPs</th> </tr> </thead> <tbody> <tr> <td>SDS-NO1</td> <td></td> <td>10.196.227.41</td> </tr> <tr> <td>SDS-NO2</td> <td></td> <td>10.196.227.41</td> </tr> <tr> <td>SDS-QS1</td> <td></td> <td>10.196.227.41</td> </tr> </tbody> </table>	Server	Node HA Pref	VIPs	SDS-NO1		10.196.227.41	SDS-NO2		10.196.227.41	SDS-QS1		10.196.227.41									
Server	Node HA Pref	VIPs																								
SDS-NO1		10.196.227.41																								
SDS-NO2		10.196.227.41																								
SDS-QS1		10.196.227.41																								
<p>3.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Verify and restart the servers</p>	<ol style="list-style-type: none"> <li>Navigate to <b>Status &amp; Manage &gt; Server</b>.                      </li> <li>Verify the DB status is <b>Norm</b> and the Proc status is <b>Man</b>.                     <p><b>Main Menu: Status &amp; Manage -&gt; Server</b></p>  <p>Buttons: Stop, Restart, Reboot, NTP Sync, Report</p> <p>Restart selected server(s).</p> </li> <li>Select the Query server and click <b>Restart</b>.</li> <li>Click <b>OK</b> on the confirmation screen.                     <p>A confirmation banner displays.</p> <p><b>Main Menu: Status &amp; Manage -&gt; Server</b></p>  </li> <li>Verify the Appl state is <b>Enabled</b> and the Alm, DB, Reporting Status, and Proc is <b>Norm</b>.</li> </ol>																								

**Procedure 10. Add Query Server to the SDS Server Group**

Step	Procedure	Description
		<p>Main Menu: Status &amp; Manage -&gt; Server</p>  <p><b>Note:</b> To refresh the server status screen before the 15-30 second default, navigate to the <b>Status &amp; Manage &gt; Server</b> screen again.</p>


**3.4 OAM Installation for DR SDS NOAM Site (Optional)**

**Assumptions:**




- This procedure assumes the SDS Network Element XML file for Disaster Recovery Provisioning SDS site has previously been created as described in Appendix A Create an XML file for Installing SDS Network Elements.
- This procedure assumes that the Network Element XML files are on the laptop’s hard drive.

This procedure requires a connection to the SDS GUI before configuring the first SDS server.

**Procedure 11. Configure DR NOAM Servers (DR SDS NOAM Site Only)**

Step	Procedure	Description
1. <input type="checkbox"/>	<b>DR SDS NOAM-A:</b> Launch a web browser.	<p>Connect to the XMI virtual IP address assigned to active SDS site using <b>https://</b>.</p> <p>If the Security Certificate Warning screen displays, click <b>Continue to this website (not recommended)</b>.</p> 

**Procedure 11. Configure DR NOAM Servers (DR SDS NOAM Site Only)**

Step	Procedure	Description
<p>2.</p> <p><input type="checkbox"/></p>	<p><b>DR SDS NOAM-A: Login</b></p>	<p>Establish a GUI session as the <b>guiadmin</b> user on the NOAM-A server.</p>  <p>Welcome to the Oracle System Login.</p> <p>This application is designed to work with most modern HTML5 compliant browsers and uses both JavaScript and cookies. Please refer to the <a href="#">Oracle Software Web Browser Support Policy</a> for details.</p> <p>Unauthorized access is prohibited.</p>
<p>3.</p> <p><input type="checkbox"/></p>	<p><b>DR SDS NOAM-A: Create the SDS VIP network element using the XML file</b></p>	<p>1. Navigate to <b>Configuration &gt; Networking &gt; Networks</b>.</p>  <p>Click <b>Browse</b> and type the pathname of the NOAM network XML file.</p>  <p><b>Note:</b> This step assumes the <b>XML</b> files were previously prepared as described in Appendix A Create an XML file for Installing SDS Network Elements.</p> <p>2. Select the location of the <b>XML</b> file and click <b>Open</b>.</p>

**Procedure 11. Configure DR NOAM Servers (DR SDS NOAM Site Only)**

Step	Procedure	Description
		<div data-bbox="516 296 1437 877"> </div> <p data-bbox="516 892 1047 926">3. Click <b>Upload File</b> to upload the XML file.</p> <p data-bbox="537 945 1252 976">To create a new Network Element, upload a valid configuration file:</p> <div data-bbox="542 982 1177 1045"> </div> <p data-bbox="516 1066 1287 1098">If the values in the <b>XML</b> file pass, an information banner displays.</p> <p data-bbox="516 1115 1190 1146"><b>Main Menu: Configuration -&gt; Networking -&gt; Networks</b></p> <div data-bbox="516 1157 1442 1339"> </div> <p data-bbox="516 1358 1404 1390"><b>Note:</b> You may need to left-click on the Info banner to display the banner.</p>



**Procedure 11. Configure DR NOAM Servers (DR SDS NOAM Site Only)**

Step	Procedure	Description														
<p>4.</p> <p><input type="checkbox"/></p>	<p><b>DR SDS NOAM-A:</b> Insert the DR NOAM-A and DR NOAM-B servers</p>	<ol style="list-style-type: none"> <li>Navigate to <b>Configuration &gt; Servers</b>.                     <ul style="list-style-type: none"> <li>Main Menu                             <ul style="list-style-type: none"> <li>Administration</li> <li>Configuration                                     <ul style="list-style-type: none"> <li>Networking   <ul style="list-style-type: none"> <li>Servers</li> <li>Server Groups</li> <li>Resource Domains</li> <li>Places</li> <li>Place Associations</li> </ul> </li> </ul> </li> </ul> </li> </ul> </li> <li>Click <b>Insert</b> to insert the new NOAM server into servers table (the first or server).</li> <li>Fill in the fields as follows:                     <p><b>Hostname:</b> Assigned Hostname  <b>Role:</b> NETWORK OAM&amp;P  <b>System ID:</b> Assigned Hostname  <b>Hardware Profile:</b> SDS Cloud Guest  <b>Network Element Name:</b> [Select NE from list]  <b>Location:</b> Optional</p> <table border="1" data-bbox="526 1031 1255 1822"> <thead> <tr> <th>Attribute</th> <th>Value</th> </tr> </thead> <tbody> <tr> <td>Hostname *</td> <td>SDS-DR-NO1</td> </tr> <tr> <td>Role *</td> <td>NETWORK OAM&amp;P</td> </tr> <tr> <td>System ID</td> <td>SDS-DR-NO1</td> </tr> <tr> <td>Hardware Profile</td> <td>DSR Guest</td> </tr> <tr> <td>Network Element Name *</td> <td>DR_SDS_OVM_NO_NE</td> </tr> <tr> <td>Location</td> <td>Bangalore</td> </tr> </tbody> </table> </li> </ol>	Attribute	Value	Hostname *	SDS-DR-NO1	Role *	NETWORK OAM&P	System ID	SDS-DR-NO1	Hardware Profile	DSR Guest	Network Element Name *	DR_SDS_OVM_NO_NE	Location	Bangalore
Attribute	Value															
Hostname *	SDS-DR-NO1															
Role *	NETWORK OAM&P															
System ID	SDS-DR-NO1															
Hardware Profile	DSR Guest															
Network Element Name *	DR_SDS_OVM_NO_NE															
Location	Bangalore															

**Procedure 11. Configure DR NOAM Servers (DR SDS NOAM Site Only)**

Step	Procedure	Description																										
<p>5.</p> <p><input type="checkbox"/></p>	<p><b>DR SDS NOAM-A:</b> Insert the 1st VM</p>	<p>The network interface fields are now available with selection choices based on the chosen hardware profile and network element.</p> <div data-bbox="526 380 1435 751" style="border: 1px solid gray; padding: 5px;"> <p><b>OAM Interfaces [At least one interface is required]:</b></p> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 40%;">Network</th> <th style="width: 30%;">IP Address</th> <th style="width: 30%;">Interface</th> </tr> </thead> <tbody> <tr> <td>INTERNALXMI (10.196.227.0/24)</td> <td>10.196.227.33</td> <td>eth0 <input type="checkbox"/> VLAN (6)</td> </tr> <tr> <td>INTERNALIMI (169.254.1.0/24)</td> <td>169.254.1.33</td> <td>eth1 <input type="checkbox"/> VLAN (3)</td> </tr> </tbody> </table> <p><b>NTP Servers:</b></p> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 60%;">NTP Server IP Address</th> <th style="width: 20%;">Prefer</th> <th style="width: 20%;"></th> </tr> </thead> <tbody> <tr> <td>10.240.191.174</td> <td><input checked="" type="checkbox"/></td> <td style="text-align: right;"><b>Add</b></td> </tr> <tr> <td></td> <td></td> <td style="text-align: right;"><b>Remove</b></td> </tr> </tbody> </table> <p style="text-align: left;"><b>Ok</b> <b>Apply</b> <b>Cancel</b></p> </div> <ol style="list-style-type: none"> <li>1. Type the server IP addresses for the XMI network. Select <b>ethX</b> for the interface. Leave the <b>VLAN</b> checkbox unchecked.</li> <li>2. Type the server IP addresses for the IMI network. Select <b>ethX</b> for the interface. Leave the <b>VLAN</b> checkbox unchecked.</li> </ol> <p><b>Note:</b> For OpenStack, these IP addresses must be the addresses used during instance booting and networking.</p> <ol style="list-style-type: none"> <li>3. Click <b>Add</b> in the NTP servers box.</li> <li>4. Add the following NTP servers:</li> </ol> <table border="1" style="width: 100%; border-collapse: collapse; margin-top: 10px;"> <thead> <tr> <th style="width: 60%;">NTP Server</th> <th style="width: 40%;">Preferred?</th> </tr> </thead> <tbody> <tr> <td>Valid NTP Server</td> <td>Yes</td> </tr> <tr> <td>Valid NTP Server (Optional)</td> <td>No</td> </tr> <tr> <td>Valid NTP Server (Optional)</td> <td>No</td> </tr> </tbody> </table> <ol style="list-style-type: none"> <li>5. Optionally, mark the <b>Prefer</b> checkbox to prefer one server over the other.</li> <li>6. Click <b>OK</b> when you have completed entering all the server data.</li> </ol>	Network	IP Address	Interface	INTERNALXMI (10.196.227.0/24)	10.196.227.33	eth0 <input type="checkbox"/> VLAN (6)	INTERNALIMI (169.254.1.0/24)	169.254.1.33	eth1 <input type="checkbox"/> VLAN (3)	NTP Server IP Address	Prefer		10.240.191.174	<input checked="" type="checkbox"/>	<b>Add</b>			<b>Remove</b>	NTP Server	Preferred?	Valid NTP Server	Yes	Valid NTP Server (Optional)	No	Valid NTP Server (Optional)	No
Network	IP Address	Interface																										
INTERNALXMI (10.196.227.0/24)	10.196.227.33	eth0 <input type="checkbox"/> VLAN (6)																										
INTERNALIMI (169.254.1.0/24)	169.254.1.33	eth1 <input type="checkbox"/> VLAN (3)																										
NTP Server IP Address	Prefer																											
10.240.191.174	<input checked="" type="checkbox"/>	<b>Add</b>																										
		<b>Remove</b>																										
NTP Server	Preferred?																											
Valid NTP Server	Yes																											
Valid NTP Server (Optional)	No																											
Valid NTP Server (Optional)	No																											

**Procedure 11. Configure DR NOAM Servers (DR SDS NOAM Site Only)**

Step	Procedure	Description
6. <input type="checkbox"/>	<b>DR SDS NOAM-A:</b> Export the initial configuration	<p>1. Navigate to <b>Configuration &gt; Servers</b>.</p>  <p>2. From the GUI screen, select the SDS server and click <b>Export</b> to generate the initial configuration data for that server. Go to the Info tab to confirm the file has been created.</p> 
7. <input type="checkbox"/>	<b>DR SDS NOAM-A:</b> Copy server configuration file to /var/tmp directory	<p>1. Obtain a terminal window to the SDS NOAM-A server, logging in as the <b>admusr</b> user.</p> <p>2. Copy the configuration file created in the previous step from the <b>/var/TKLC/db/filemgmt</b> directory on the SDS NOAM-A to the <b>/var/tmp</b> directory. The configuration file has a filename like <b>TKLCConfigData.&lt;hostname&gt;.sh</b>. The following is an example:</p> <pre>\$ cp /var/TKLC/db/filemgmt/TKLCConfigData.&lt;hostname&gt;.sh /var/tmp/TKLCConfigData.sh</pre> <p><b>Note:</b> The server polls the /var/tmp directory for the configuration file and automatically executes it.</p> <p>For the NOAM-B server, the command is:</p> <pre>\$ scp \ /var/TKLC/db/filemgmt/TKLCConfigData.&lt;hostname&gt;.sh \ &lt;ipaddr&gt;:/var/tmp/TKLCConfigData.sh</pre> <p><b>Note:</b> The IPADDR is the IP address of NOAM-B associated with the XMI network.</p>





**Procedure 11. Configure DR NOAM Servers (DR SDS NOAM Site Only)**

Step	Procedure	Description
8. <input type="checkbox"/>	<b>DR SDS NOAM-A:</b> Wait for configuration to complete	<p>The automatic configuration daemon looks for the file named <b>TKLCConfigData.sh</b> in the <b>/var/tmp</b> directory, implements the configuration in the file, and prompts the user to reboot the server.</p> <p>A broadcast message is sent to the terminal. This can take anywhere from 3-20 minutes to complete.</p> <p>If you are on the console, wait to be prompted to reboot the server, but <b>DO NOT</b> reboot the server, it is rebooted later in this procedure.</p> <p>Verify the script completed successfully by checking the following file.</p> <pre>\$ sudo cat /var/TKLC/appw/logs/Process/install.log</pre> <p><b>Note:</b> Ignore the warning about removing the USB key since no USB key is present. No response occurs until the reboot prompt is issued.</p>
9. <input type="checkbox"/>	<b>DR SDS NOAM-A:</b> Verify server health	<ol style="list-style-type: none"> <li>Log into the NOAM1 as the <b>admusr</b> user.</li> <li>Execute the following command on the 1<sup>st</sup> NOAM server and make sure no errors are returned: <pre>\$ sudo syscheck Running modules in class hardware... OK Running modules in class disk... OK Running modules in class net... OK Running modules in class system... OK Running modules in class proc... OK LOG LOCATION: /var/TKLC/log/syscheck/fail_log</pre> </li> </ol>
10. <input type="checkbox"/>	<b>DR SDS NOAM-A:</b> Verify server health	<p>Exit from the command line to return to the server console.</p> <pre>\$ exit sds-mrsvnc-a login:</pre>
11. <input type="checkbox"/>	<b>DR SDS NOAM-B:</b> Repeat	Configure DR SDS NOAM-B by repeating steps 4. through 10. of this procedure.




### 3.5 OAM Pairing for DR SDS NOAM Site (Optional)

During the OAM pairing procedure, various errors may display at different stages of the procedure. During the execution of a step, ignore errors related to values other than the ones referenced by that step.

#### Procedure 12. Pair the DR OAM Servers (DR SDS NOAM Site Only)

Step	Procedure	Description
1. <input type="checkbox"/>	<b>Primary SDS VIP:</b> Launch a web browser	<p>Connect to the XMI virtual IP address assigned to Primary SDS NOAM-A site using <b>https://</b>.</p> <p>If the Security Certificate Warning screen displays, click <b>Continue to this website (not recommended)</b>.</p> 
2. <input type="checkbox"/>	<b>Primary SDS VIP:</b> Login	<p>Establish a GUI session as the <b>default</b> user.</p> 

**Procedure 12. Pair the DR OAM Servers (DR SDS NOAM Site Only)**

Step	Procedure	Description
<p>3.</p> <p><input type="checkbox"/></p>	<p><b>DR SDS NOAM-A:</b> Enter group data</p>	<p>1. Navigate to <b>Configuration &gt; Server Groups</b>.</p>  <p>2. Click <b>Insert</b>.</p>  <p>3. Fill in the following fields:</p> <p><b>Server Group Name:</b> [Type DR Server Group Name]  <b>Level:</b> A  <b>Parent:</b> None  <b>Function:</b> SDS  <b>WAN Replication Connection Count:</b> Use Default Value</p> <p><b>Main Menu: Configuration -&gt; Server Groups [Insert]</b></p>  <p>4. Click <b>OK</b> when all fields are filled in.</p>



**Procedure 12. Pair the DR OAM Servers (DR SDS NOAM Site Only)**

Step	Procedure	Description																			
<p>4.</p> <p><input type="checkbox"/></p>	<p><b>DR SDS NOAM-A:</b> Add server to OAM Server Group</p>	<p>1. Select the new server group and click <b>Edit</b>.</p> <p><b>Main Menu: Configuration -&gt; Server Groups</b></p> <p>Filter* ▾</p> <table border="1"> <thead> <tr> <th>Server Group Name</th> <th>Level</th> <th>Parent</th> <th>Function</th> <th>Connection Count</th> </tr> </thead> <tbody> <tr> <td>DR_NO_SG</td> <td>A</td> <td>NONE</td> <td>SDS</td> <td>1</td> </tr> </tbody> </table> <p>Insert Edit Delete Report</p> <p>2. In the portion of the screen that lists the servers for the server group, find the SDS-NOAM servers being configured. Mark the <b>Include in SG</b> checkbox.</p> <p>SDS_OVM_NO_NE <input type="checkbox"/> Prefer Network Element as spare</p> <table border="1"> <thead> <tr> <th>Server</th> <th>SG Inclusion</th> <th>Preferred HA Role</th> </tr> </thead> <tbody> <tr> <td>SDS-DR-NO1</td> <td><input checked="" type="checkbox"/> Include in SG</td> <td><input type="checkbox"/> Prefer server as spare</td> </tr> <tr> <td>SDS-DR-NO2</td> <td><input checked="" type="checkbox"/> Include in SG</td> <td><input type="checkbox"/> Prefer server as spare</td> </tr> </tbody> </table> <p>VIP Assignment</p> <p>VIP Address <input type="text"/> Add</p> <p>Ok Apply Cancel</p> <p>3. Leave other boxes unchecked.</p> <p>4. Click <b>Apply</b>.</p>	Server Group Name	Level	Parent	Function	Connection Count	DR_NO_SG	A	NONE	SDS	1	Server	SG Inclusion	Preferred HA Role	SDS-DR-NO1	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare	SDS-DR-NO2	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare
Server Group Name	Level	Parent	Function	Connection Count																	
DR_NO_SG	A	NONE	SDS	1																	
Server	SG Inclusion	Preferred HA Role																			
SDS-DR-NO1	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare																			
SDS-DR-NO2	<input checked="" type="checkbox"/> Include in SG	<input type="checkbox"/> Prefer server as spare																			

**Procedure 12. Pair the DR OAM Servers (DR SDS NOAM Site Only)**

Step	Procedure	Description
5. <input type="checkbox"/>	<b>DR SDS NOAM-A:</b> Add VIP address	<p>1. Click <b>Add</b>.</p> <div data-bbox="521 352 1341 527"> </div> <p>2. Type the <b>VIP Address</b> and click <b>Apply</b>.</p> <div data-bbox="521 590 1365 911"> </div> <p>This process takes a minimum of 5 minutes, depending on the underlying infrastructure. The server pairs within the server group and establishes a master/slave relationship for High Availability (HA).</p>



**Procedure 12. Pair the DR OAM Servers (DR SDS NOAM Site Only)**

Step	Procedure	Description																																										
<p>6.</p> <p><input type="checkbox"/></p>	<p><b>DR SDS VIP:</b> Verify and restart the servers</p>	<p>1. Navigate to <b>Status &amp; Manage &gt; Server</b>.</p>  <p>2. Verify the DB status is <b>Norm</b> and the Proc status is <b>Man</b>.</p> <p><b>Main Menu: Status &amp; Manage -&gt; Server</b></p> <table border="1" data-bbox="519 819 1429 1050"> <thead> <tr> <th>Server Hostname</th> <th>Network Element</th> <th>Appl State</th> <th>Alm</th> <th>DB</th> <th>Reporting Status</th> <th>Proc</th> </tr> </thead> <tbody> <tr> <td>SDS-N01</td> <td>SDS_OVM_NO_NE</td> <td>Disabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Man</td> </tr> <tr> <td>SDS-N02</td> <td>SDS_OVM_NO_NE</td> <td>Disabled</td> <td>Warn</td> <td>Norm</td> <td>Norm</td> <td>Man</td> </tr> </tbody> </table> <p>3. Select the SDS NOAM-A server and click <b>Restart</b>.</p> <p>4. Click <b>OK</b> on the confirmation screen.</p> <p>A confirmation banner displays</p> <p><b>Main Menu: Status &amp; Manage -&gt; Server</b></p>  <p>5. Verify the Appl state is <b>Enabled</b> and the DB and Reporting Status is <b>Norm</b>.</p> <p><b>Main Menu: Status &amp; Manage -&gt; Server</b></p> <table border="1" data-bbox="519 1596 1429 1722"> <thead> <tr> <th>Server Hostname</th> <th>Network Element</th> <th>Appl State</th> <th>Alm</th> <th>DB</th> <th>Reporting Status</th> <th>Proc</th> </tr> </thead> <tbody> <tr> <td>SDS-N01</td> <td>SDS_OVM_NO_NE</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-N02</td> <td>SDS_OVM_NO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> </tbody> </table> <p><b>Note:</b> To refresh the server status screen before the 15-30 second default, navigate to the <b>Status &amp; Manage &gt; Server</b> screen again.</p>	Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc	SDS-N01	SDS_OVM_NO_NE	Disabled	Err	Norm	Norm	Man	SDS-N02	SDS_OVM_NO_NE	Disabled	Warn	Norm	Norm	Man	Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc	SDS-N01	SDS_OVM_NO_NE	Enabled	Err	Norm	Norm	Norm	SDS-N02	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm
Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc																																						
SDS-N01	SDS_OVM_NO_NE	Disabled	Err	Norm	Norm	Man																																						
SDS-N02	SDS_OVM_NO_NE	Disabled	Warn	Norm	Norm	Man																																						
Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc																																						
SDS-N01	SDS_OVM_NO_NE	Enabled	Err	Norm	Norm	Norm																																						
SDS-N02	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm																																						

**Procedure 12. Pair the DR OAM Servers (DR SDS NOAM Site Only)**

Step	Procedure	Description
7. <input type="checkbox"/>	<b>DR SDS NOAM-B:</b> Repeat	Configure SDS NOAM-B by repeating step 6 of this procedure. This process takes a minimum of 5 minutes, depending on the underlying infrastructure. The server pairs within the server group and establishes a master/slave relationship for High Availability (HA).

**Procedure 13. Verify SDS Server Alarm Status**

Step	Procedure	Description																
1. <input type="checkbox"/>	<b>SDS VIP:</b> Establish GUI session on the NOAM VIP	<p>Establish a GUI session on the NOAM by using the NOAM VIP address. Login as the <b>guiadmin</b> user.</p>  <p>Welcome to the Oracle System Login.</p> <p>This application is designed to work with most modern HTML5 compliant browsers and uses both JavaScript and cookies. Please refer to the <a href="#">Oracle Software Web Browser Support Policy</a> for details.</p> <p>Unauthorized access is prohibited.</p>																
2. <input type="checkbox"/>	<b>SDS VIP:</b> Wait for remote database alarm to clear	<ol style="list-style-type: none"> <li>Navigate to <b>Alarms &amp; Events &gt; View Active</b>.</li> <li>Verify Event ID <b>14101</b> (No Remote Connections) is the only alarm present on the system at this time.</li> </ol> <p><b>Main Menu: Alarms &amp; Events -&gt; View Active (Filtered)</b></p>  <table border="1"> <thead> <tr> <th>Seq #</th> <th>Event ID</th> <th>Timestamp</th> <th>Severity</th> <th>Product</th> <th>Process</th> <th>NE</th> <th>Server</th> </tr> </thead> <tbody> <tr> <td>83</td> <td>14101</td> <td>2016-06-20 13:29:49.058 EDT</td> <td>MAJOR</td> <td>SDS</td> <td>xds</td> <td>SDS_OVM_NO_NE</td> <td>SDS-NO1</td> </tr> </tbody> </table> <p>No Remote Connections</p> <p>GN_JINFOWRN for information only (Listener:C:453) ** No XML client connect... <a href="#">More...</a></p>	Seq #	Event ID	Timestamp	Severity	Product	Process	NE	Server	83	14101	2016-06-20 13:29:49.058 EDT	MAJOR	SDS	xds	SDS_OVM_NO_NE	SDS-NO1
Seq #	Event ID	Timestamp	Severity	Product	Process	NE	Server											
83	14101	2016-06-20 13:29:49.058 EDT	MAJOR	SDS	xds	SDS_OVM_NO_NE	SDS-NO1											

**Procedure 13. Verify SDS Server Alarm Status**


Step	Procedure	Description
3. <input type="checkbox"/>	<b>SDS VIP:</b> Add Query server for the DR SDS server	Repeat all steps in Section 3.3 except use the DR SDS NOAM NE and server group instead of the primary SDS NOAM NE and server group.

**3.6 OAM Installation for DP-SOAM Sites (All DP-SOAM Sites)****Assumptions:**

- This procedure assumes the DP-SOAM Network Element XML file for the DP-SOMA site has previously been created as described in Appendix A Create an XML file for Installing SDS Network Elements.
- This procedure assumes that the Network Element XML files are on the laptop's hard drive.




This procedure is for installing the DP-SOAM software on the OAM server located at each DSR Signaling Site. The DP-SOAM and DSR OAM servers run on two virtual machines.

**Procedure 14. OAM Installation for DP-SOAM Servers**




Step	Procedure	Description
1. <input type="checkbox"/>	<b>Active SDS VIP:</b> Launch a web browser	<p>Connect to the XMI virtual IP address assigned to active SDS site using <b>https://</b>.</p> <p>If the Security Certificate Warning screen displays, click <b>Continue to this website (not recommended)</b>.</p> 



**Procedure 14. OAM Installation for DP-SOAM Servers**

Step	Procedure	Description
<p>2.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP: Login</b></p>	<p>Establish a GUI session as the guiadmin user on the NOAM-A server.</p>  <p>Welcome to the Oracle System Login.</p> <p>This application is designed to work with most modern HTML5 compliant browsers and uses both JavaScript and cookies. Please refer to the <a href="#">Oracle Software Web Browser Support Policy</a> for details.</p> <p>Unauthorized access is prohibited.</p>
<p>3.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP: Configure the DP SOAM network element</b></p>	<p>1. Navigate to <b>Configuration &gt; Networking &gt; Networks</b>.</p>  <p>Click <b>Browse</b> and type the pathname of the NOAM network XML file.</p>  <p><b>Note:</b> This step assumes the <b>XML</b> files were previously prepared as described in Appendix A Create an XML file for Installing SDS Network Elements.</p> <p>2. Select the location of the <b>XML</b> file and click <b>Open</b>.</p>

**Procedure 14. OAM Installation for DP-SOAM Servers**

Step	Procedure	Description
		 <p>3. Click <b>Upload File</b> to upload the XML file.</p> <p>To create a new Network Element, upload a valid configuration file:</p> <p><input type="button" value="Browse..."/> SO_NE_OVM.xml <input type="button" value="Upload File"/></p> <p>Copyright © 2010, 2016, Oracle and/or its affiliates. All rights reserved.</p> <p>If the values in the <b>XML</b> file pass, an information banner displays.</p> <p><b>Main Menu: Configuration -&gt; Networking -&gt; Networks</b></p>  <p><b>Note:</b> You may need to left-click on the Info banner to display the banner.</p>
4.	<p><b>Active SDS VIP:</b> Configure the SOAM server</p>	<p>1. Navigate to <b>Configuration &gt; Servers</b>.</p>  <p>2. Click <b>Insert</b> to insert the new SOAM server into servers table.</p>


**Procedure 14. OAM Installation for DP-SOAM Servers**

Step	Procedure	Description																																		
		<p><b>Main Menu: Configuration -&gt; Servers</b></p> <p>Filter* <input type="text"/></p> <table border="1"> <thead> <tr> <th>Hostname</th> <th>Role</th> <th>System ID</th> <th>Server Group</th> <th>Network Element</th> </tr> </thead> <tbody> <tr> <td>SDS-NO1</td> <td>Network OAM&amp;P</td> <td>SDS-NO1</td> <td>NO_SG</td> <td>SDS_OVM_NO_M</td> </tr> <tr> <td>SDS-NO2</td> <td>Network OAM&amp;P</td> <td>SDS-NO2</td> <td>NO_SG</td> <td>SDS_OVM_NO_M</td> </tr> <tr> <td>SDS-QS1</td> <td>Query Server</td> <td></td> <td>NO_SG</td> <td>SDS_OVM_NO_M</td> </tr> </tbody> </table> <p><input type="button" value="Insert"/> <input type="button" value="Edit"/> <input type="button" value="Delete"/> <input type="button" value="Export"/> <input type="button" value="Report"/></p> <p>3. Fill in the fields as follows:</p> <p><b>Hostname:</b> Assigned Hostname  <b>Role:</b> <a href="#">SYSTEM OAM</a>  <b>System ID:</b> Assigned Hostname  <b>Hardware Profile:</b> <a href="#">SDS Cloud Guest</a>  <b>Network Element Name:</b> [Select NE from list]  <b>Location:</b> Optional</p> <p><b>Main Menu: Configuration -&gt; Servers [Insert]</b></p> <hr/> <p><b>Adding a new server</b></p> <table border="1"> <thead> <tr> <th>Attribute</th> <th>Value</th> </tr> </thead> <tbody> <tr> <td>Hostname *</td> <td><input type="text" value="SDS-SO1"/></td> </tr> <tr> <td>Role *</td> <td><input type="text" value="SYSTEM OAM"/> <input type="button" value="v"/></td> </tr> <tr> <td>System ID</td> <td><input type="text" value="SDS-SO1"/></td> </tr> <tr> <td>Hardware Profile</td> <td><input type="text" value="SDS Cloud Guest"/> <input type="button" value="v"/></td> </tr> <tr> <td>Network Element Name *</td> <td><input type="text" value="SDS_OVM_SO_NE"/> <input type="button" value="v"/></td> </tr> <tr> <td>Location</td> <td><input type="text" value="Bangalore"/></td> </tr> </tbody> </table>	Hostname	Role	System ID	Server Group	Network Element	SDS-NO1	Network OAM&P	SDS-NO1	NO_SG	SDS_OVM_NO_M	SDS-NO2	Network OAM&P	SDS-NO2	NO_SG	SDS_OVM_NO_M	SDS-QS1	Query Server		NO_SG	SDS_OVM_NO_M	Attribute	Value	Hostname *	<input type="text" value="SDS-SO1"/>	Role *	<input type="text" value="SYSTEM OAM"/> <input type="button" value="v"/>	System ID	<input type="text" value="SDS-SO1"/>	Hardware Profile	<input type="text" value="SDS Cloud Guest"/> <input type="button" value="v"/>	Network Element Name *	<input type="text" value="SDS_OVM_SO_NE"/> <input type="button" value="v"/>	Location	<input type="text" value="Bangalore"/>
Hostname	Role	System ID	Server Group	Network Element																																
SDS-NO1	Network OAM&P	SDS-NO1	NO_SG	SDS_OVM_NO_M																																
SDS-NO2	Network OAM&P	SDS-NO2	NO_SG	SDS_OVM_NO_M																																
SDS-QS1	Query Server		NO_SG	SDS_OVM_NO_M																																
Attribute	Value																																			
Hostname *	<input type="text" value="SDS-SO1"/>																																			
Role *	<input type="text" value="SYSTEM OAM"/> <input type="button" value="v"/>																																			
System ID	<input type="text" value="SDS-SO1"/>																																			
Hardware Profile	<input type="text" value="SDS Cloud Guest"/> <input type="button" value="v"/>																																			
Network Element Name *	<input type="text" value="SDS_OVM_SO_NE"/> <input type="button" value="v"/>																																			
Location	<input type="text" value="Bangalore"/>																																			

**Procedure 14. OAM Installation for DP-SOAM Servers**

Step	Procedure	Description																							
<p>5.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Insert the network element</p>	<p>The network interface fields are now available with selection choices based on the chosen hardware profile and network element.</p> <div data-bbox="526 380 1442 787" style="border: 1px solid #ccc; padding: 5px;"> <p><b>OAM Interfaces [At least one interface is required.]:</b></p> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 40%;">Network</th> <th style="width: 30%;">IP Address</th> <th style="width: 30%;">Interface</th> </tr> </thead> <tbody> <tr> <td>INTERNALXMI (10.196.227.0/24)</td> <td>10.196.227.35</td> <td>eth0 <input type="checkbox"/> VLAN (6)</td> </tr> <tr> <td>INTERNALIMI (169.254.1.0/24)</td> <td>169.254.1.35</td> <td>eth1 <input type="checkbox"/> VLAN (3)</td> </tr> </tbody> </table> <p><b>NTP Servers:</b></p> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 60%;">NTP Server IP Address</th> <th style="width: 20%;">Prefer</th> <th style="width: 20%;"></th> </tr> </thead> <tbody> <tr> <td>10.240.191.174</td> <td><input checked="" type="checkbox"/></td> <td style="text-align: right;"> <input type="button" value="Add"/> <input type="button" value="Remove"/> </td> </tr> </tbody> </table> <p style="text-align: left;"> <input type="button" value="Ok"/> <input type="button" value="Apply"/> <input type="button" value="Cancel"/> </p> </div> <ol style="list-style-type: none"> <li>1. Type the server IP addresses for the XMI network. Select <b>ethX</b> for the interface. Leave the <b>VLAN</b> checkbox unchecked.</li> <li>2. Type the server IP addresses for the IMI network. Select <b>ethX</b> for the interface. Leave the <b>VLAN</b> checkbox unchecked.</li> </ol> <p><b>Note:</b> For OpenStack, these IP addresses must be the addresses used during instance booting and networking.</p> <ol style="list-style-type: none"> <li>3. Add the following NTP servers:</li> </ol> <table border="1" style="width: 100%; border-collapse: collapse; margin: 10px 0;"> <thead> <tr> <th style="width: 60%;">NTP Server</th> <th style="width: 40%;">Preferred?</th> </tr> </thead> <tbody> <tr> <td>Valid NTP Server</td> <td>Yes</td> </tr> <tr> <td>Valid NTP Server (Optional)</td> <td>No</td> </tr> <tr> <td>Valid NTP Server (Optional)</td> <td>No</td> </tr> </tbody> </table> <ol style="list-style-type: none"> <li>4. Optionally, mark the <b>Prefer</b> checkbox to prefer one server over the other.</li> <li>5. Click <b>OK</b> when you have completed entering all the server data.</li> </ol>	Network	IP Address	Interface	INTERNALXMI (10.196.227.0/24)	10.196.227.35	eth0 <input type="checkbox"/> VLAN (6)	INTERNALIMI (169.254.1.0/24)	169.254.1.35	eth1 <input type="checkbox"/> VLAN (3)	NTP Server IP Address	Prefer		10.240.191.174	<input checked="" type="checkbox"/>	<input type="button" value="Add"/> <input type="button" value="Remove"/>	NTP Server	Preferred?	Valid NTP Server	Yes	Valid NTP Server (Optional)	No	Valid NTP Server (Optional)	No
Network	IP Address	Interface																							
INTERNALXMI (10.196.227.0/24)	10.196.227.35	eth0 <input type="checkbox"/> VLAN (6)																							
INTERNALIMI (169.254.1.0/24)	169.254.1.35	eth1 <input type="checkbox"/> VLAN (3)																							
NTP Server IP Address	Prefer																								
10.240.191.174	<input checked="" type="checkbox"/>	<input type="button" value="Add"/> <input type="button" value="Remove"/>																							
NTP Server	Preferred?																								
Valid NTP Server	Yes																								
Valid NTP Server (Optional)	No																								
Valid NTP Server (Optional)	No																								

## Procedure 14. OAM Installation for DP-SOAM Servers

Step	Procedure	Description																														
6. <input type="checkbox"/>	<b>Active SDS VIP:</b> Export the initial configuration	<p>1. Navigate to <b>Configuration &gt; Servers</b>.</p>  <p>2. From the GUI screen, select the SDS server and click <b>Export</b> to generate the initial configuration data for that server. Go to the Info tab to confirm the file has been created.</p> <p><b>Main Menu: Configuration -&gt; Servers</b></p> <table border="1"> <thead> <tr> <th>Hostname</th> <th>Role</th> <th>System ID</th> <th>Server Group</th> <th>Network Element</th> <th>Location</th> </tr> </thead> <tbody> <tr> <td>SDS-NO1</td> <td>Network OAM&amp;P</td> <td>SDS-NO1</td> <td>NO_SG</td> <td>SDS_OVM_NO_NE</td> <td>Bangalore</td> </tr> <tr> <td>SDS-NO2</td> <td>Network OAM&amp;P</td> <td>SDS-NO2</td> <td>NO_SG</td> <td>SDS_OVM_NO_NE</td> <td>Bangalore</td> </tr> <tr> <td>SDS-QS1</td> <td>Query Server</td> <td></td> <td>NO_SG</td> <td>SDS_OVM_NO_NE</td> <td>Bangalore</td> </tr> <tr style="background-color: #e6f2ff;"> <td>SDS-S01</td> <td>System OAM</td> <td>SDS-S01</td> <td>SO_SG</td> <td>SDS_OVM_SO_NE</td> <td>Bangalore</td> </tr> </tbody> </table> <p><b>Insert</b> <b>Edit</b> <b>Delete</b> <b>Export</b> <b>Report</b></p>	Hostname	Role	System ID	Server Group	Network Element	Location	SDS-NO1	Network OAM&P	SDS-NO1	NO_SG	SDS_OVM_NO_NE	Bangalore	SDS-NO2	Network OAM&P	SDS-NO2	NO_SG	SDS_OVM_NO_NE	Bangalore	SDS-QS1	Query Server		NO_SG	SDS_OVM_NO_NE	Bangalore	SDS-S01	System OAM	SDS-S01	SO_SG	SDS_OVM_SO_NE	Bangalore
Hostname	Role	System ID	Server Group	Network Element	Location																											
SDS-NO1	Network OAM&P	SDS-NO1	NO_SG	SDS_OVM_NO_NE	Bangalore																											
SDS-NO2	Network OAM&P	SDS-NO2	NO_SG	SDS_OVM_NO_NE	Bangalore																											
SDS-QS1	Query Server		NO_SG	SDS_OVM_NO_NE	Bangalore																											
SDS-S01	System OAM	SDS-S01	SO_SG	SDS_OVM_SO_NE	Bangalore																											
7. <input type="checkbox"/>	<b>Active SDS VIP:</b> Copy server configuration file to /var/tmp directory	<p>1. Obtain a terminal window to the SDS NOAM-A server, logging in as the <b>admusr</b> user.</p> <p>2. Copy the configuration file created in the previous step from the <b>/var/TKLC/db/filegmt</b> directory on the SDS NOAM-A to the <b>/var/tmp</b> directory. The configuration file has a filename like <b>TKLCConfigData.&lt;hostname&gt;.sh</b>. The following is an example:</p> <pre>\$ cp /var/TKLC/db/filegmt/TKLCConfigData.&lt;NOAM-A_hostname&gt;.sh /var/tmp/TKLCConfigData.sh</pre> <p><b>Note:</b> The server polls the /var/tmp directory for the configuration file and automatically executes it.</p> <p>For the NOAM-B server, the command is:</p> <pre>\$ scp \ /var/TKLC/db/filegmt/TKLCConfigData.&lt;NOAM-B_hostname&gt;.sh \ &lt;NOAM-B_ipaddr&gt;:/var/tmp/TKLCConfigData.sh</pre> <p><b>Note:</b> The IPADDR is the IP address of NOAM-B associated with the XMI network.</p>																														



**Procedure 14. OAM Installation for DP-SOAM Servers**

Step	Procedure	Description
8. <input type="checkbox"/>	<b>SDS SOAM Server:</b> Wait for configuration to complete	<p>The automatic configuration daemon looks for the file named <b>TKLCConfigData.sh</b> in the <b>/var/tmp</b> directory, implements the configuration in the file, and prompts the user to reboot the server.</p> <p>A broadcast message is sent to the terminal. This can take anywhere from 3-20 minutes to complete.</p> <p>If you are on the console, wait to be prompted to reboot the server, but <b>DO NOT</b> reboot the server, it is rebooted later in this procedure.</p> <p>Verify the script completed successfully by checking the following file.</p> <pre>\$ sudo cat /var/TKLC/appw/logs/Process/install.log</pre> <p><b>Note:</b> Ignore the warning about removing the USB key since no USB key is present. No response occurs until the reboot prompt is issued.</p>
9. <input type="checkbox"/>	<b>SDS SOAM Server:</b> Set the time zone (Optional) and reboot the server	<ol style="list-style-type: none"> <li>To change the system time zone, from the command line prompt, execute <b>set_ini_tz.pl</b>. The following command example uses the America/New_York time zone.</li> <li>Replace, as appropriate, with the time zone you have selected for this installation. For a full list of valid time zones, see Appendix B List of Frequently Used Time Zones.</li> </ol> <pre>\$ sudo /usr/TKLC/appworks/bin/set_ini_tz.pl "America/New_York" &gt;/dev/null 2&gt;&amp;1 \$ sudo init 6</pre> <ol style="list-style-type: none"> <li>Wait for server to reboot.</li> </ol>
10. <input type="checkbox"/>	<b>SDS NOAM-A:</b> Verify server health	<ol style="list-style-type: none"> <li>Log into the NOAM1 as the <b>admusr</b> user.</li> <li>Execute the following command on the 1<sup>st</sup> NOAM server and make sure no errors are returned: <pre>\$ sudo syscheck Running modules in class hardware... OK Running modules in class disk... OK Running modules in class net... OK Running modules in class system... OK Running modules in class proc... OK LOG LOCATION: /var/TKLC/log/syscheck/fail_log</pre> </li> </ol>
11. <input type="checkbox"/>	<b>SDS NOAM-B:</b> Repeat	Configure DR SDS NOAM-B by repeating steps 4. through 10. of this procedure.




### 3.7 OAM Pairing for DP-SOAM Sites (All DP-SOAM Sites)

During the OAM pairing procedure, various errors may display at different stages of the procedure. During the execution of a step, ignore errors related to values other than the ones referenced by that step.

#### Procedure 15. Pair the OAM Servers for DP-SOAM Sites




Step	Procedure	Description
1. <input type="checkbox"/>	<b>Active SDS VIP:</b> Launch a web browser.	<p>Connect to the XMI virtual IP address assigned to active SDS site using <b>https://</b>.</p> <p>If the Security Certificate Warning screen displays, click <b>Continue to this website (not recommended)</b>.</p> 
2. <input type="checkbox"/>	<b>Active SDS VIP:</b> Login	<p>Establish a GUI session as the <b>default</b> user.</p> 

**Procedure 15. Pair the OAM Servers for DP-SOAM Sites**



Step	Procedure	Description
<p>3.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Enter group data</p>	<p>1. Navigate to <b>Configuration &gt; Server Groups</b>.</p>  <p>2. Click <b>Insert</b>.</p>  <p>3. Fill in the following fields:</p> <p><b>Server Group Name:</b> [Type Server Group Name]  <b>Level:</b> B  <b>Parent:</b> [Select SDS Server Group Name from Procedure 3, step 4. ]  <b>Function:</b> SDS  <b>WAN Replication Connection Count:</b> Use Default Value</p> <p><b>Main Menu: Configuration -&gt; Server Groups [Insert]</b></p>  <p>4. Click <b>OK</b> when all fields are filled in.</p>



**Procedure 15. Pair the OAM Servers for DP-SOAM Sites**

Step	Procedure	Description
<p>4.</p> <p><input type="checkbox"/></p>	<p><b>SDS SOAM-A:</b> Add server to OAM Server Group</p>	<p>1. Select the new server group and click <b>Edit</b>.</p> <p>Main Menu: Configuration -&gt; Server Groups</p>  <p>2. In the portion of the screen that lists the servers for the server group, find the SDS-NOAM servers being configured. Mark the <b>Include in SG</b> checkbox.</p>  <p>3. Leave other boxes unchecked.</p> <p>4. Click <b>Apply</b>.</p>
<p>5.</p> <p><input type="checkbox"/></p>	<p><b>SDS SOAM-A:</b> Add VIP address</p>	<p>1. Click <b>Add</b>.</p> <p>2. Type the <b>VIP Address</b> and click <b>OK</b>.</p>  <p>This process takes a minimum of 5 minutes, depending on the underlying infrastructure. The server pairs within the server group and establishes a master/slave relationship for High Availability (HA).</p>



**Procedure 15. Pair the OAM Servers for DP-SOAM Sites**

Step	Procedure	Description																																																																																				
<p>6.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Verify and restart the servers</p>	<p>1. Navigate to <b>Status &amp; Manage &gt; Server</b>.</p>  <p>2. Verify the DB status is <b>Norm</b> and the Proc status is <b>Man</b>.</p> <p>Main Menu: Status &amp; Manage -&gt; Server</p> <p>Tue Aug 02:02:38:14 2016 ED</p> <table border="1" data-bbox="516 808 1442 1039"> <thead> <tr> <th>Server Hostname</th> <th>Network Element</th> <th>Appl State</th> <th>Alm</th> <th>DB</th> <th>Reporting Status</th> <th>Proc</th> </tr> </thead> <tbody> <tr> <td>SDS-DR-NO1</td> <td>SDS_OVM_DR_NO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-DR-NO2</td> <td>SDS_OVM_DR_NO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-NO1</td> <td>SDS_OVM_NO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-NO2</td> <td>SDS_OVM_NO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-SO1</td> <td>SDS_OVM_SO_SE</td> <td>Disabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Man</td> </tr> <tr> <td>SDS-SO2</td> <td>SDS_OVM_SO_SE</td> <td>Disabled</td> <td>Warn</td> <td>Norm</td> <td>Norm</td> <td>Man</td> </tr> </tbody> </table> <p>3. Select the DP SOAM-A server and click <b>Restart</b>.</p> <p>4. Click <b>OK</b> on the confirmation screen.</p> <p>A confirmation banner displays.</p> <p><b>Main Menu: Status &amp; Manage -&gt; Server</b></p>  <p>5. Verify the Appl state is <b>Enabled</b> and the DB and Reporting Status is <b>Norm</b>.</p> <p>Main Menu: Status &amp; Manage -&gt; Server</p> <p>Wed Jun 22 00:15</p> <table border="1" data-bbox="516 1533 1442 1648"> <thead> <tr> <th>Server Hostname</th> <th>Network Element</th> <th>Appl State</th> <th>Alm</th> <th>DB</th> <th>Reporting Status</th> <th>Proc</th> </tr> </thead> <tbody> <tr> <td>SDS-NO1</td> <td>SDS_OVM_NO_NE</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-NO2</td> <td>SDS_OVM_NO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-OS1</td> <td>SDS_OVM_NO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-SO1</td> <td>SDS_OVM_SO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> </tbody> </table> <p><b>Note:</b> To refresh the server status screen before the 15-30 second default, navigate to the <b>Status &amp; Manage &gt; Server</b> screen again.</p>	Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc	SDS-DR-NO1	SDS_OVM_DR_NO_NE	Enabled	Norm	Norm	Norm	Norm	SDS-DR-NO2	SDS_OVM_DR_NO_NE	Enabled	Norm	Norm	Norm	Norm	SDS-NO1	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm	SDS-NO2	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm	SDS-SO1	SDS_OVM_SO_SE	Disabled	Err	Norm	Norm	Man	SDS-SO2	SDS_OVM_SO_SE	Disabled	Warn	Norm	Norm	Man	Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc	SDS-NO1	SDS_OVM_NO_NE	Enabled	Err	Norm	Norm	Norm	SDS-NO2	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm	SDS-OS1	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm	SDS-SO1	SDS_OVM_SO_NE	Enabled	Norm	Norm	Norm	Norm
Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc																																																																																
SDS-DR-NO1	SDS_OVM_DR_NO_NE	Enabled	Norm	Norm	Norm	Norm																																																																																
SDS-DR-NO2	SDS_OVM_DR_NO_NE	Enabled	Norm	Norm	Norm	Norm																																																																																
SDS-NO1	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm																																																																																
SDS-NO2	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm																																																																																
SDS-SO1	SDS_OVM_SO_SE	Disabled	Err	Norm	Norm	Man																																																																																
SDS-SO2	SDS_OVM_SO_SE	Disabled	Warn	Norm	Norm	Man																																																																																
Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc																																																																																
SDS-NO1	SDS_OVM_NO_NE	Enabled	Err	Norm	Norm	Norm																																																																																
SDS-NO2	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm																																																																																
SDS-OS1	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm																																																																																
SDS-SO1	SDS_OVM_SO_NE	Enabled	Norm	Norm	Norm	Norm																																																																																
<p>7.</p> <p><input type="checkbox"/></p>	<p><b>SDS SOAM-B:</b> Repeat</p>	<p>Configure SDS SOAM-B by repeating step 7 of this procedure.</p> <p>This process takes a minimum of 5 minutes, depending on the underlying infrastructure. The server pairs within the server group and establishes a master/slave relationship for High Availability (HA).</p>																																																																																				

### 3.8 DP Installation (All DP-SOAM Sites)

During the Data Processor (DP) installation procedure, various errors may display at different stages of the procedure. During the execution of a step, ignore errors related to values other than the ones referenced by that step

#### Procedure 16. Configure the Database Processor (DP) Server

Step	Procedure	Description
<p>1.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Launch a web browser.</p>	<p>Connect to the XMI virtual IP address assigned to active SDS site using <b>https://</b>.</p> <p>If the Security Certificate Warning screen displays, click <b>Continue to this website (not recommended)</b>.</p> 
<p>2.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Login</p>	<p>Establish a GUI session as the <b>guiadmin</b> user on the NOAM-A server.</p> 

**Procedure 16. Configure the Database Processor (DP) Server**

Step	Procedure	Description														
<p>3.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Configure DP server</p>	<ol style="list-style-type: none"> <li>Navigate to <b>Configuration &gt; Servers</b>.                     <ul style="list-style-type: none"> <li>Main Menu                             <ul style="list-style-type: none"> <li>Administration</li> <li>Configuration                                     <ul style="list-style-type: none"> <li>Networking   <ul style="list-style-type: none"> <li>Servers</li> <li>Server Groups</li> <li>Resource Domains</li> <li>Places</li> <li>Place Associations</li> </ul> </li> </ul> </li> </ul> </li> </ul> </li> <li>Click <b>Insert</b> to insert the new NOAM server into servers table (the first or server).</li> <li>Fill in the fields as follows:                     <p><b>Hostname:</b> Assigned Hostname</p> <p><b>Role:</b> MP</p> <p><b>System ID:</b> Leave Blank</p> <p><b>Hardware Profile:</b> SDS Cloud Guest</p> <p><b>Network Element Name:</b> [Select <b>NE</b> from list where Query server is physically located]</p> <p><b>Location:</b> Optional</p> <p><b>Main Menu: Configuration -&gt; Servers [Insert]</b></p> <hr/> <p><b>Adding a new server</b></p> <table border="1"> <thead> <tr> <th>Attribute</th> <th>Value</th> </tr> </thead> <tbody> <tr> <td>Hostname *</td> <td>SDS-DP1</td> </tr> <tr> <td>Role *</td> <td>MP</td> </tr> <tr> <td>System ID</td> <td></td> </tr> <tr> <td>Hardware Profile</td> <td>SDS Cloud Guest</td> </tr> <tr> <td>Network Element Name *</td> <td>SDS_OVM_SO_NE</td> </tr> <tr> <td>Location</td> <td>Bangalore</td> </tr> </tbody> </table> </li> </ol>	Attribute	Value	Hostname *	SDS-DP1	Role *	MP	System ID		Hardware Profile	SDS Cloud Guest	Network Element Name *	SDS_OVM_SO_NE	Location	Bangalore
Attribute	Value															
Hostname *	SDS-DP1															
Role *	MP															
System ID																
Hardware Profile	SDS Cloud Guest															
Network Element Name *	SDS_OVM_SO_NE															
Location	Bangalore															

**Procedure 16. Configure the Database Processor (DP) Server**

Step	Procedure	Description																												
<p>4.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Insert the DP server</p>	<p>The network interface fields are now available with selection choices based on the chosen hardware profile and network element.</p> <div data-bbox="521 380 1414 814" style="border: 1px solid #ccc; padding: 5px;"> <p><b>OAM Interfaces [At least one interface is required.]:</b></p> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 30%;">Network</th> <th style="width: 30%;">IP Address</th> <th style="width: 40%;">Interface</th> </tr> </thead> <tbody> <tr> <td>INTERNALXMI (10.196.227.0/24)</td> <td>10.196.227.36</td> <td>eth0 <input type="checkbox"/> VLAN (6)</td> </tr> <tr> <td>INTERNALIMI (169.254.1.0/24)</td> <td>169.254.1.36</td> <td>eth1 <input type="checkbox"/> VLAN (3)</td> </tr> </tbody> </table> <p><b>NTP Servers:</b></p> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 50%;">NTP Server IP Address</th> <th style="width: 30%;">Prefer</th> <th style="width: 20%;"></th> </tr> </thead> <tbody> <tr> <td>10.240.191.174</td> <td><input type="checkbox"/></td> <td style="text-align: right;"> <input type="button" value="Add"/> <input type="button" value="Remove"/> </td> </tr> </tbody> </table> <p> <input type="button" value="Ok"/> <input type="button" value="Apply"/> <input type="button" value="Cancel"/> </p> </div> <ol style="list-style-type: none"> <li>1. Type the server IP addresses for the XMI network. Select <b>ethX</b> for the interface. Leave the <b>VLAN</b> checkbox unchecked.</li> <li>2. Type the server IP addresses for the IMI network. Select <b>ethX</b> for the interface. Leave the <b>VLAN</b> checkbox unchecked.</li> </ol> <p><b>Note:</b> For OpenStack, these IP addresses must be the addresses used during instance booting and networking.</p> <p>Add the following NTP servers:</p> <table border="1" style="width: 100%; border-collapse: collapse; margin: 10px 0;"> <thead> <tr> <th style="width: 60%;">NTP Server</th> <th style="width: 40%;">Preferred?</th> </tr> </thead> <tbody> <tr> <td>Valid NTP Server</td> <td>Yes</td> </tr> <tr> <td>Valid NTP Server (Optional)</td> <td>No</td> </tr> <tr> <td>Valid NTP Server (Optional)</td> <td>No</td> </tr> </tbody> </table> <ol style="list-style-type: none"> <li>3. Optionally, mark the <b>Prefer</b> checkbox to prefer one server over the other.</li> <li>4. Click <b>OK</b> when you have completed entering all the server data.</li> </ol>	Network	IP Address	Interface	INTERNALXMI (10.196.227.0/24)	10.196.227.36	eth0 <input type="checkbox"/> VLAN (6)	INTERNALIMI (169.254.1.0/24)	169.254.1.36	eth1 <input type="checkbox"/> VLAN (3)	NTP Server IP Address	Prefer		10.240.191.174	<input type="checkbox"/>	<input type="button" value="Add"/> <input type="button" value="Remove"/>	NTP Server	Preferred?	Valid NTP Server	Yes	Valid NTP Server (Optional)	No	Valid NTP Server (Optional)	No					
Network	IP Address	Interface																												
INTERNALXMI (10.196.227.0/24)	10.196.227.36	eth0 <input type="checkbox"/> VLAN (6)																												
INTERNALIMI (169.254.1.0/24)	169.254.1.36	eth1 <input type="checkbox"/> VLAN (3)																												
NTP Server IP Address	Prefer																													
10.240.191.174	<input type="checkbox"/>	<input type="button" value="Add"/> <input type="button" value="Remove"/>																												
NTP Server	Preferred?																													
Valid NTP Server	Yes																													
Valid NTP Server (Optional)	No																													
Valid NTP Server (Optional)	No																													
<p>5.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Export the initial configuration</p>	<p>From the GUI screen, select the SDS server and click <b>Export</b> to generate the initial configuration data for that server. Go to the Info tab to confirm the file has been created.</p> <div data-bbox="521 1528 1414 1822" style="border: 1px solid #ccc; padding: 5px;"> <p><b>Main Menu: Configuration -&gt; Servers</b></p> <p>Filter* <input type="text"/></p> <table border="1" style="width: 100%; border-collapse: collapse;"> <thead> <tr> <th style="width: 15%;">Hostname</th> <th style="width: 15%;">Role</th> <th style="width: 15%;">System ID</th> <th style="width: 15%;">Server Group</th> <th style="width: 15%;">Network Element</th> <th style="width: 15%;">Location</th> <th style="width: 10%;">Place</th> </tr> </thead> <tbody> <tr> <td>SDS-N01</td> <td>Network OAM&amp;P</td> <td>SDS-N01</td> <td>NO_80</td> <td>SDS_OVM_NO_NE</td> <td>Bangalore</td> <td></td> </tr> <tr> <td>SDS-N02</td> <td>Network OAM&amp;P</td> <td>SDS-N02</td> <td>NO_80</td> <td>SDS_OVM_NO_NE</td> <td>Bangalore</td> <td></td> </tr> <tr style="background-color: #e0f0ff;"> <td>SDS-QS1</td> <td>Query Server</td> <td></td> <td></td> <td>SDS_OVM_NO_NE</td> <td>Bangalore</td> <td></td> </tr> </tbody> </table> <p style="text-align: center;"> <input type="button" value="Insert"/> <input type="button" value="Edit"/> <input type="button" value="Delete"/> <input style="color: blue;" type="button" value="Export"/> <input type="button" value="Report"/> </p> </div>	Hostname	Role	System ID	Server Group	Network Element	Location	Place	SDS-N01	Network OAM&P	SDS-N01	NO_80	SDS_OVM_NO_NE	Bangalore		SDS-N02	Network OAM&P	SDS-N02	NO_80	SDS_OVM_NO_NE	Bangalore		SDS-QS1	Query Server			SDS_OVM_NO_NE	Bangalore	
Hostname	Role	System ID	Server Group	Network Element	Location	Place																								
SDS-N01	Network OAM&P	SDS-N01	NO_80	SDS_OVM_NO_NE	Bangalore																									
SDS-N02	Network OAM&P	SDS-N02	NO_80	SDS_OVM_NO_NE	Bangalore																									
SDS-QS1	Query Server			SDS_OVM_NO_NE	Bangalore																									



**Procedure 16. Configure the Database Processor (DP) Server**

Step	Procedure	Description
6. <input type="checkbox"/>	<b>Active SDS VIP:</b> Login and change directory	<ol style="list-style-type: none"> <li>Obtain a terminal window to the active SDS VIP server, logging in as the <b>admusr</b> user.</li> <li>Change directory to filemgmt:  <pre>\$ cd /var/TKLC/db/filemgmt</pre> </li> </ol>
7. <input type="checkbox"/>	<b>Active SDS VIP:</b> Copy server configuration file to /var/tmp directory	<p>Copy the configuration file created in the previous step from the <b>/var/TKLC/db/filemgmt</b> directory on the active SDS VIP to the <b>/var/tmp</b> directory. The configuration file has a filename like <b>TKLCConfigData.&lt;hostname&gt;.sh</b>. The following is an example:</p> <pre>\$ scp \ /var/TKLC/db/filemgmt/TKLCConfigData.&lt;hostname&gt;.sh \ &lt;ipaddr&gt;:/var/tmp/TKLCConfigData.sh</pre> <p><b>Note:</b> The IPADDR is the IP address of the DP server associated with the XMI network.</p>
8. <input type="checkbox"/>	<b>DP Server:</b> Wait for configuration to complete	<p>The automatic configuration daemon looks for the file named <b>TKLCConfigData.sh</b> in the <b>/var/tmp</b> directory, implements the configuration in the file, and prompts the user to reboot the server.</p> <p>A broadcast message is sent to the terminal. This can take anywhere from 3-20 minutes to complete.</p> <p>If you are on the console, wait to be prompted to reboot the server, but <b>DO NOT</b> reboot the server, it is rebooted later in this procedure.</p> <p>Verify the script completed successfully by checking the following file.</p> <pre>\$ sudo cat /var/TKLC/appw/logs/Process/install.log</pre> <p><b>Note:</b> Ignore the warning about removing the USB key since no USB key is present. No response occurs until the reboot prompt is issued.</p>
9. <input type="checkbox"/>	<b>DP Server:</b> Set the time zone (Optional) and reboot the server	<ol style="list-style-type: none"> <li>To change the system time zone, from the command line prompt, execute <b>set_ini_tz.pl</b>. The following command example uses the America/New_York time zone.</li> <li>Replace, as appropriate, with the time zone you have selected for this installation. For a full list of valid time zones, see Appendix B List of Frequently Used Time Zones.  <pre>\$ sudo /usr/TKLC/appworks/bin/set_ini_tz.pl "America/New_York" &gt;/dev/null 2&gt;&amp;1 \$ sudo init 6</pre> </li> <li>Wait for server to reboot.</li> </ol>

**Procedure 16. Configure the Database Processor (DP) Server**




Step	Procedure	Description
10. <input type="checkbox"/>	<b>DP Server:</b> Verify server health	1. Log into the NOAM1 as the <b>admusr</b> user. 2. Execute the following command on the 1 <sup>st</sup> NOAM server and make sure no errors are returned: <pre> \$ sudo syscheck Running modules in class hardware...                                 OK Running modules in class disk...                                 OK Running modules in class net...                                 OK Running modules in class system...                                 OK Running modules in class proc...                                 OK LOG LOCATION: /var/TKLC/log/syscheck/fail_log </pre>
11. <input type="checkbox"/>	<b>Active SDS VIP:</b> Repeat	For additional DP servers, repeat steps 3. through 10. of this procedure.

**Procedure 17. Add DP Server to the SDS Server Group**


Step	Procedure	Description																		
<p>1.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Add server to OAM Server Group</p>	<p>1. Navigate to <b>Configuration &gt; Server Groups</b>.</p>  <p>2. Click <b>Insert</b>.</p>  <p>3. Fill in the following fields:</p> <p><b>Server Group Name:</b> [Type Server Group Name]  <b>Level:</b> C  <b>Parent:</b> [Select System OAM Group Name]  <b>Function:</b> SDS  <b>WAN Replication Connection Count:</b> Use Default Value</p> <p><b>Main Menu: Configuration -&gt; Server Groups [Insert]</b></p> <hr/> <p><b>Adding new server group</b></p> <table border="1" data-bbox="527 1207 1437 1690"> <thead> <tr> <th>Field</th> <th>Value</th> <th>Description</th> </tr> </thead> <tbody> <tr> <td>Server Group Name *</td> <td>DP_SG</td> <td>Unique identifier used to label a Server Group. [De least one alpha and must not start with a digit] [A v</td> </tr> <tr> <td>Level *</td> <td>C</td> <td>Select one of the Levels supported by the system [</td> </tr> <tr> <td>Parent *</td> <td>SO_SG</td> <td>Select an existing Server Group [A value is requirec</td> </tr> <tr> <td>Function *</td> <td>SDS</td> <td>Select one of the Functions supported by the syste</td> </tr> <tr> <td>WAN Replication Connection Count</td> <td>1</td> <td>Specify the number of TCP connections that will be between 1 and 8.]</td> </tr> </tbody> </table> <p>4. Click <b>OK</b> when all fields are filled in.</p>	Field	Value	Description	Server Group Name *	DP_SG	Unique identifier used to label a Server Group. [De least one alpha and must not start with a digit] [A v	Level *	C	Select one of the Levels supported by the system [	Parent *	SO_SG	Select an existing Server Group [A value is requirec	Function *	SDS	Select one of the Functions supported by the syste	WAN Replication Connection Count	1	Specify the number of TCP connections that will be between 1 and 8.]
Field	Value	Description																		
Server Group Name *	DP_SG	Unique identifier used to label a Server Group. [De least one alpha and must not start with a digit] [A v																		
Level *	C	Select one of the Levels supported by the system [																		
Parent *	SO_SG	Select an existing Server Group [A value is requirec																		
Function *	SDS	Select one of the Functions supported by the syste																		
WAN Replication Connection Count	1	Specify the number of TCP connections that will be between 1 and 8.]																		



**Procedure 17. Add DP Server to the SDS Server Group**

Step	Procedure	Description
<p>2.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Add server to OAM Server Group</p>	<p>1. Select the new server group and click <b>Edit</b>.</p> <p>Main Menu: Configuration -&gt; Server Groups</p>  <p>2. In the portion of the screen that lists the servers for the server group, find the SDS-NOAM servers being configured. Mark the <b>Include in SG</b> checkbox.</p>  <p>3. Leave other boxes unchecked.</p> <p>4. Click <b>Apply</b>.</p> <p>A confirmation banner displays.</p> <p><b>Main Menu: Configuration -&gt; Server Gr</b></p> 
<p>3.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Repeat</p>	<p>For each subtending DP server, repeat steps 1. and 2. of this procedure. This process takes a minimum of 5 minutes, depending on the underlying infrastructure. The servers establish DB replication with the active DP-SOAM server at the NE.</p>



**Procedure 17. Add DP Server to the SDS Server Group**

Step	Procedure	Description																																																																																																		
<p>4.</p> <p><input type="checkbox"/></p>	<p><b>SDS VIP:</b> Verify and restart the servers</p>	<p>1. Navigate to <b>Status &amp; Manage &gt; Server</b>.</p>  <p>2. Verify the DB and Reporting Status are <b>Norm</b> and the Proc status is <b>Man</b>.</p> <p>Main Menu: Status &amp; Manage -&gt; Server <span style="float: right;">Wed Jun 22 00:1</span></p> <table border="1" data-bbox="516 800 1442 972"> <thead> <tr> <th>Server Hostname</th> <th>Network Element</th> <th>Appl State</th> <th>Alm</th> <th>DB</th> <th>Reporting Status</th> <th>Proc</th> </tr> </thead> <tbody> <tr> <td>SDS-N01</td> <td>SDS_OVM_NO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-N02</td> <td>SDS_OVM_NO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-Q01</td> <td>SDS_OVM_NO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-S01</td> <td>SDS_OVM_SO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-S02</td> <td>SDS_OVM_SO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-DP1</td> <td>SDS_OVM_SO_NE</td> <td>Disabled</td> <td>Warn</td> <td>Norm</td> <td>Norm</td> <td>Man</td> </tr> </tbody> </table> <p>3. Select the DP server and click <b>Restart</b>.</p> <p>4. Click <b>OK</b> on the confirmation screen.</p> <p>Are you sure you wish to restart application software on the following server(s)? SDS-DP1</p> <div style="text-align: center; border: 1px solid gray; padding: 5px; width: fit-content; margin: 0 auto;"> <input type="button" value="OK"/> <input type="button" value="Cancel"/> </div> <p>A confirmation <b>Successfully restarted application</b> banner displays.</p> <p>5. Verify the Appl state is <b>Enabled</b> and the Alm, DB, Reporting Status, and Proc are <b>Norm</b>.</p> <p>Main Menu: Status &amp; Manage -&gt; Server <span style="float: right;">Wed Jun 22 02:09:28 2016 EDT</span></p> <table border="1" data-bbox="516 1476 1442 1629"> <thead> <tr> <th>Server Hostname</th> <th>Network Element</th> <th>Appl State</th> <th>Alm</th> <th>DB</th> <th>Reporting Status</th> <th>Proc</th> </tr> </thead> <tbody> <tr> <td>SDS-DP1</td> <td>SDS_OVM_SO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-DP2</td> <td>SDS_OVM_SO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-N01</td> <td>SDS_OVM_NO_NE</td> <td>Enabled</td> <td>Err</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-N02</td> <td>SDS_OVM_NO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-Q01</td> <td>SDS_OVM_NO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> <tr> <td>SDS-S01</td> <td>SDS_OVM_SO_NE</td> <td>Enabled</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> <td>Norm</td> </tr> </tbody> </table> <p><b>Note:</b> To refresh the server status screen before the 15-30 second default, navigate to the <b>Status &amp; Manage &gt; Server</b> screen again.</p>	Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc	SDS-N01	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm	SDS-N02	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm	SDS-Q01	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm	SDS-S01	SDS_OVM_SO_NE	Enabled	Norm	Norm	Norm	Norm	SDS-S02	SDS_OVM_SO_NE	Enabled	Norm	Norm	Norm	Norm	SDS-DP1	SDS_OVM_SO_NE	Disabled	Warn	Norm	Norm	Man	Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc	SDS-DP1	SDS_OVM_SO_NE	Enabled	Norm	Norm	Norm	Norm	SDS-DP2	SDS_OVM_SO_NE	Enabled	Norm	Norm	Norm	Norm	SDS-N01	SDS_OVM_NO_NE	Enabled	Err	Norm	Norm	Norm	SDS-N02	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm	SDS-Q01	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm	SDS-S01	SDS_OVM_SO_NE	Enabled	Norm	Norm	Norm	Norm
Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc																																																																																														
SDS-N01	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm																																																																																														
SDS-N02	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm																																																																																														
SDS-Q01	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm																																																																																														
SDS-S01	SDS_OVM_SO_NE	Enabled	Norm	Norm	Norm	Norm																																																																																														
SDS-S02	SDS_OVM_SO_NE	Enabled	Norm	Norm	Norm	Norm																																																																																														
SDS-DP1	SDS_OVM_SO_NE	Disabled	Warn	Norm	Norm	Man																																																																																														
Server Hostname	Network Element	Appl State	Alm	DB	Reporting Status	Proc																																																																																														
SDS-DP1	SDS_OVM_SO_NE	Enabled	Norm	Norm	Norm	Norm																																																																																														
SDS-DP2	SDS_OVM_SO_NE	Enabled	Norm	Norm	Norm	Norm																																																																																														
SDS-N01	SDS_OVM_NO_NE	Enabled	Err	Norm	Norm	Norm																																																																																														
SDS-N02	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm																																																																																														
SDS-Q01	SDS_OVM_NO_NE	Enabled	Norm	Norm	Norm	Norm																																																																																														
SDS-S01	SDS_OVM_SO_NE	Enabled	Norm	Norm	Norm	Norm																																																																																														
<p>5.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Repeat</p>	<p>For each additional DP server, repeat step 3. of this procedure.</p>																																																																																																		

### 3.9 Configure ComAgent

This procedure configures ComAgent, which allows the SDS data processor servers and DSR message processor servers to communicate with each other. These steps cannot be executed until all SDS DP servers are configured.

#### Procedure 18. Configure ComAgent (All DP-SOAM Sites)

Step	Procedure	Description
1. <input type="checkbox"/>	<b>Active SDS VIP:</b> Open a web browser	<p>Connect to the XMI virtual IP address assigned to active SDS site using <b>https://</b>.</p> <p>If the Security Certificate Warning screen displays, click <b>Continue to this website (not recommended)</b>.</p> 
2. <input type="checkbox"/>	<b>Active SDS VIP:</b> Login	<p>Establish a GUI session as the <b>default</b> user.</p> 


**Procedure 18. Configure ComAgent (All DP-SOAM Sites)**

Step	Procedure	Description
<p>3.</p> <p><input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Navigate to Remote Servers screen</p>	<p>1. Navigate to <b>Administration &gt; Remote Servers</b>.</p> <ul style="list-style-type: none"> <li>- Main Menu               <ul style="list-style-type: none"> <li>+ Administration</li> <li>+ Configuration</li> <li>+ Alarms &amp; Events</li> <li>+ Security Log</li> <li>+ Status &amp; Manage</li> <li>+ Measurements</li> <li>- Communication Agent                   <ul style="list-style-type: none"> <li>- Configuration                       <ul style="list-style-type: none"> <li>Remote Servers</li> <li>Connection Groups</li> <li>Routed Services</li> </ul> </li> <li>+ Maintenance</li> </ul> </li> <li>+ SDS</li> </ul> </li> </ul> <p>2. Click <b>Insert</b>.</p>

**Procedure 18. Configure ComAgent (All DP-SOAM Sites)**

Step	Procedure	Description
<p>4. <input type="checkbox"/></p>	<p><b>Active SDS VIP:</b> Configure the Remote server</p>	<p>1. Type the <b>Remote Server Name</b> for the DSR Message Processor server.</p> <p>Remote Server Name * <input type="text"/></p> <p>2. Type the <b>Remote Server IPv4 Address</b>.</p> <p>Remote Server IPv4 IP Address <input type="text"/></p> <p><b>Note:</b> This is the IMI IP address of the MP.</p> <p>3. Type the <b>Remote Server IPv6 Address</b>.</p> <p>Remote Server IPv6 IP Address <input type="text"/></p> <p>4. Select the <b>IP Address Preference</b>.</p> <p>IP Address Preference <input type="text" value="ComAgent Network Preference"/></p> <p>5. Select <b>Client</b> for the Remote Server Mode.</p> <p>Remote Server Mode * <input type="text" value="Client"/> <div style="border: 1px solid black; padding: 2px; margin-top: 2px;">             Client              -- Select --              Client              Server           </div> </p> <p>6. Select the <b>Local Server Group</b> for the SDS Data Processor server group.</p> <div style="border: 1px solid gray; padding: 5px; margin-top: 5px;"> <p>Available Local Server Groups</p> <div style="border: 1px solid gray; padding: 2px; margin-bottom: 5px;">DP_SG</div> <p style="text-align: center;">Add selected Local Server Group(s).</p> <div style="display: flex; justify-content: space-around; align-items: center;"> <span>&gt;&gt;</span> <span>&lt;&lt;</span> </div> <p>Assigned Local Server Groups</p> <div style="border: 1px solid gray; height: 20px; width: 100%;"></div> </div> <p>7. Click <b>Apply</b>.</p>

**Procedure 18. Configure ComAgent (All DP-SOAM Sites)**

Step	Procedure	Description
5. <input type="checkbox"/>	<b>Active SDS VIP:</b> Confirm data information	<p>A confirmation banner displays.</p> <p><b>Main Menu: Communication Agent -&gt; Configuration -&gt; Remote Servers [Insert]</b></p> 
6. <input type="checkbox"/>	Active SDS VIP: Repeat	For each remote MP in the same SOAM NE, repeat steps 3. through 5. of this procedure.

**3.10 Backups and Disaster Prevention**


The preferred method for backing up cloud system VM instances is by snapshotting. Once the DSR and optional sub-systems are installed and configured, but before adding traffic, use the appropriate cloud tool such as the VMware Manager or the OpenStack Horizon GUI, to take snapshots of critical VM instances. It is particularly important to snapshot the control instances, such as the NOAM and SOAM.

**Note:** To be on the safe side, follow this procedure to back up the NOAM and SOAM database.



**3.11 Backups and Disaster Prevention****Procedure 19. Backups and Disaster Prevention**

Step	Procedure	Description
1. <input type="checkbox"/>	Identify Backup Server	<p>Identify an external server to be used as a backup server for the following steps. The server should not be co-located with any of the following items:</p> <ul style="list-style-type: none"> <li>• Cloud Infrastructure Manager Server/Controller</li> <li>• SDS NOAM</li> </ul>

**Procedure 19. Backups and Disaster Prevention**





Step	Procedure	Description
<p>2.</p> <p><input type="checkbox"/></p>	<p><b>NOAM VIP:</b> Login</p>	<p>Establish a GUI session as the <b>guiadmin</b> user on the NOAM.</p>  <p>Welcome to the Oracle System Login.</p> <p>This application is designed to work with most modern HTML5 compliant browsers and uses both JavaScript and cookies. Please refer to the <a href="#">Oracle Software Web Browser Support Policy</a> for details.</p> <p>Unauthorized access is prohibited.</p> <hr/> <p><i>Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.</i></p> <p><i>Copyright © 2010, 2017, <a href="#">Oracle</a> and/or its affiliates. All rights reserved.</i></p>

**Procedure 19. Backups and Disaster Prevention**

Step	Procedure	Description												
<p>3.</p> <p><input type="checkbox"/></p>	<p><b>NOAM VIP:</b> Backup Configuration Data for the System</p>	<p>1. Navigate to <b>Status &amp; Manage &gt; Database</b>.</p>  <p>2. Select the active NOAM server and click <b>Backup</b>.</p>  <p>3. Make sure <b>Configuration</b> checkbox is marked.</p> <p><b>Database Backup</b></p> <table border="1" data-bbox="516 945 1412 1564"> <thead> <tr> <th>Field</th> <th>Value</th> </tr> </thead> <tbody> <tr> <td colspan="2">Server: SDS-NO</td> </tr> <tr> <td>Select data for backup</td> <td> <input type="checkbox"/> Provisioning  <input checked="" type="checkbox"/> Configuration                 </td> </tr> <tr> <td>Compression *</td> <td> <input type="radio"/> gzip  <input checked="" type="radio"/> bzip2  <input type="radio"/> none                 </td> </tr> <tr> <td>Archive Name *</td> <td>Backup.sds.SDS-NO.Configuration.NETWORK_OAMP.20170622_043225.MAN</td> </tr> <tr> <td>Comment</td> <td><input type="text"/></td> </tr> </tbody> </table> <p><input type="button" value="Ok"/> <input type="button" value="Cancel"/></p> <p>4. Type a filename for the backup and click <b>OK</b>.</p>	Field	Value	Server: SDS-NO		Select data for backup	<input type="checkbox"/> Provisioning <input checked="" type="checkbox"/> Configuration	Compression *	<input type="radio"/> gzip <input checked="" type="radio"/> bzip2 <input type="radio"/> none	Archive Name *	Backup.sds.SDS-NO.Configuration.NETWORK_OAMP.20170622_043225.MAN	Comment	<input type="text"/>
Field	Value													
Server: SDS-NO														
Select data for backup	<input type="checkbox"/> Provisioning <input checked="" type="checkbox"/> Configuration													
Compression *	<input type="radio"/> gzip <input checked="" type="radio"/> bzip2 <input type="radio"/> none													
Archive Name *	Backup.sds.SDS-NO.Configuration.NETWORK_OAMP.20170622_043225.MAN													
Comment	<input type="text"/>													



**Procedure 19. Backups and Disaster Prevention**

Step	Procedure	Description																								
<p>4.</p> <p><input type="checkbox"/></p>	<p><b>NOAM VIP:</b> Verify the backup file existence</p>	<p>1. Navigate to <b>Status &amp; Manage &gt; Files</b>.</p>  <p>2. Select the active NOAM tab.</p> <p>Main Menu: Status &amp; Manage -&gt; Files</p> <p>Filter: Tasks</p>  <table border="1" data-bbox="521 745 1388 892"> <thead> <tr> <th>File Name</th> <th>Size</th> <th>Type</th> <th>Timestamp</th> </tr> </thead> <tbody> <tr> <td>TKLCCnfigData.Martinique-NO1.sh</td> <td>5.1 KB</td> <td>sh</td> <td>2016-10-03 04:30:11 EDT</td> </tr> <tr> <td>TKLCCnfigData.Martinique-SO1.sh</td> <td>4 KB</td> <td>sh</td> <td>2016-10-03 01:47:08 EDT</td> </tr> <tr> <td>TKLCCnfigData.SS7-MP.sh</td> <td>6.3 KB</td> <td>sh</td> <td>2016-10-05 04:51:20 EDT</td> </tr> <tr> <td>ugwrap.log</td> <td>1.3 KB</td> <td>log</td> <td>2016-10-03 01:09:41 EDT</td> </tr> <tr> <td>upgrade.log</td> <td>209.5 KB</td> <td>log</td> <td>2016-10-03 01:19:23 EDT</td> </tr> </tbody> </table> <p>The files on this server display. Verify the existence of the backup file.</p>	File Name	Size	Type	Timestamp	TKLCCnfigData.Martinique-NO1.sh	5.1 KB	sh	2016-10-03 04:30:11 EDT	TKLCCnfigData.Martinique-SO1.sh	4 KB	sh	2016-10-03 01:47:08 EDT	TKLCCnfigData.SS7-MP.sh	6.3 KB	sh	2016-10-05 04:51:20 EDT	ugwrap.log	1.3 KB	log	2016-10-03 01:09:41 EDT	upgrade.log	209.5 KB	log	2016-10-03 01:19:23 EDT
File Name	Size	Type	Timestamp																							
TKLCCnfigData.Martinique-NO1.sh	5.1 KB	sh	2016-10-03 04:30:11 EDT																							
TKLCCnfigData.Martinique-SO1.sh	4 KB	sh	2016-10-03 01:47:08 EDT																							
TKLCCnfigData.SS7-MP.sh	6.3 KB	sh	2016-10-05 04:51:20 EDT																							
ugwrap.log	1.3 KB	log	2016-10-03 01:09:41 EDT																							
upgrade.log	209.5 KB	log	2016-10-03 01:19:23 EDT																							
<p>5.</p> <p><input type="checkbox"/></p>	<p><b>NOAM VIP:</b> Download the file to a local machine</p>	<p>1. Select the backup file.</p> <p>2. Click <b>Download</b>.</p>  <p>1.1 GB used (5.93%) of 18.4 GB available   System utilization: 1.1 GB (5.99%) of 18.4 GB available.</p> <p>3. Select <b>OK</b> to confirm the download.</p> 																								

**Procedure 19. Backups and Disaster Prevention**

Step	Procedure	Description
6. <input type="checkbox"/>	Upload the image to secure location	Transfer the backed up image saved to the secure location where the server backup files are fetched in case of system disaster recovery.

**3.12 Configure the Desired MTU value**

By default SDS defines MTU size of all its management and/or signaling networks as 1500 bytes. If the configured virtual network(s) on cloud is VXLAN based and MTU size defined/negotiated on it is 1500 bytes, then we need to accommodate VXLAN header (size 65 bytes) within these 1500 bytes.

**Procedure 20. Configure the desired MTU value**

STEP #	Procedure	Description
<p>This procedure configures the desired MTU value.</p> <p>Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.</p> <p>If this procedure fails, contact My Oracle Support (MOS) and ask for assistance.</p>		
1. <input type="checkbox"/>	Verify the MTU on SDS system	<p>Verify the MTU on SDS system, by executing:</p> <pre>iqt -pE NetworkDeviceOption</pre> <p>Sample output:</p> <pre>DeviceOption_ID=0 Keyword=MTU Device_ID=0 Value=1500 DeviceOption_ID=1 Keyword=bootProto Device_ID=0 Value=none DeviceOption_ID=2 Keyword=onboot Device_ID=0 Value=yes DeviceOption_ID=3 Keyword=MTU Device_ID=1 Value=1500 DeviceOption_ID=4 Keyword=bootProto Device_ID=1 Value=none DeviceOption_ID=5 Keyword=onboot Device_ID=1 Value=yes DeviceOption_ID=6 Keyword=MTU Device_ID=2 Value=1500 DeviceOption_ID=7 Keyword=bootProto Device_ID=2 Value=none DeviceOption_ID=8 Keyword=onboot Device_ID=2 Value=yes DeviceOption_ID=9 Keyword=MTU Device_ID=3 Value=1500 DeviceOption_ID=10 Keyword=bootProto Device_ID=3 Value=none DeviceOption_ID=11 Keyword=onboot Device_ID=3 Value=yes DeviceOption_ID=12 Keyword=MTU Device_ID=4 Value=1500 DeviceOption_ID=13 Keyword=bootProto Device_ID=4 Value=none DeviceOption_ID=14 Keyword=onboot Device_ID=4 Value=yes</pre>
2. <input type="checkbox"/>	Change the MTU value on SDS system (Optional)	<p>If the MTU value is 1500 bytes, change it to 1435 bytes, by executing:</p> <pre>sudo iset -fValue=1435 NetworkDeviceOption where "Keyword='MTU'"</pre> <pre>=== changed 256 records ===</pre> <p>Wait for few minutes.</p>

STEP #	Procedure	Description
3.	Verify the MTU value	<p>Verify the MTU value on SDS system by executing:</p> <pre>ip addr</pre> <p>Sample output:</p> <pre>1: lo: &lt;LOOPBACK,UP,LOWER_UP&gt; mtu 65536 qdisc noqueue state UNKNOWN link/loopback 00:00:00:00:00:00 brd 00:00:00:00:00:00 inet 127.0.0.1/8 scope host lo inet6 ::1/128 scope host valid_lft forever preferred_lft forever 2: control: &lt;BROADCAST,MULTICAST,UP,LOWER_UP&gt; mtu 1450 qdisc pfifo_fast state UP qlen 1000 link/ether 02:79:b5:f7:65:0e brd ff:ff:ff:ff:ff:ff inet 192.168.1.32/24 brd 192.168.1.255 scope global control inet6 fe80::79:b5ff:fe7:650e/64 scope link valid_lft forever preferred_lft forever 3: xmi: &lt;BROADCAST,MULTICAST,UP,LOWER_UP&gt; mtu 1435 qdisc pfifo_fast state UP qlen 1000 link/ether 02:90:04:c6:3b:e1 brd ff:ff:ff:ff:ff:ff inet 10.75.198.37/25 brd 10.75.198.127 scope global xmi inet 10.75.198.4/25 scope global secondary xmi inet6 2606:b400:605:b821:90:4ff:fec6:3be1/64 scope global dynamic valid_lft 2591870sec preferred_lft 604670sec inet6 fe80::90:4ff:fec6:3be1/64 scope link valid_lft forever preferred_lft forever 4: imi: &lt;BROADCAST,MULTICAST,UP,LOWER_UP&gt; mtu 1435 qdisc pfifo_fast state UP qlen 1000 link/ether 02:3b:48:96:3c:61 brd ff:ff:ff:ff:ff:ff inet 192.168.100.32/24 brd 192.168.100.255 scope global imi inet6 fe80::3b:48ff:fe96:3c61/64 scope link valid_lft forever preferred_lft forever</pre> <p>Verify on all nodes:</p> <pre>iqt -pE NetworkDeviceOption</pre> <p>Sample output:</p> <pre>DeviceOption_ID=0 Keyword=MTU Device_ID=0 Value=1435 DeviceOption_ID=1 Keyword=bootProto Device_ID=0 Value=none DeviceOption_ID=2 Keyword=onboot Device_ID=0 Value=yes DeviceOption_ID=3 Keyword=MTU Device_ID=1 Value=1435 DeviceOption_ID=4 Keyword=bootProto Device_ID=1 Value=none DeviceOption_ID=5 Keyword=onboot Device_ID=1 Value=yes DeviceOption_ID=6 Keyword=MTU Device_ID=2 Value=1435 DeviceOption_ID=7 Keyword=bootProto Device_ID=2 Value=none DeviceOption_ID=8 Keyword=onboot Device_ID=2 Value=yes DeviceOption_ID=9 Keyword=MTU Device_ID=3 Value=1435 DeviceOption_ID=10 Keyword=bootProto Device_ID=3 Value=none DeviceOption_ID=11 Keyword=onboot Device_ID=3 Value=yes DeviceOption_ID=12 Keyword=MTU Device_ID=4 Value=1435 DeviceOption_ID=13 Keyword=bootProto Device_ID=4 Value=none DeviceOption_ID=14 Keyword=onboot Device_ID=4 Value=yes</pre>

## Appendix A. Create an XML file for Installing SDS Network Elements

SDS Network Elements can be created by using an XML configuration file. The SDS software image (\*.iso) contains two examples of XML configuration files for “NO” (Network OAM&P) and “SO” (System OAM) networks. These files are named **SDS\_NO\_NE.xml** and **SDS\_SO\_NE.xml** and are stored on the **/usr/TKLC/sds/vlan** directory. The customer is required to create individual XML files for each of their SDS Network Elements. The format for each of these XML files is identical.

Below is an example of the SDS\_NO\_NE.xml file. The highlighted values are values that the user must update.

**Note:** The **Description** column in this example includes comments for this document only. **Do not include** the Description column in the actual XML file used during installation.

**Table 2. SDS XML SDS Network Element Configuration File (IPv4)**

XML File Text	Description
<?xml version="1.0"?>	
<networkelement>	
<name> <b>sds_mrsvnc</b> </name>	Unique identifier used to label a Network Element. [Range = 1-32 character string. Valid characters are alphanumeric and underscore. Must contain at least one alpha and must not start with a digit.]
<ntpserver>	
</ntpserver>	
<networks>	
<network>	
<name>XML</name>	Name of customer external network. <b>Note:</b> Do NOT change this name.
<vlanId> <b>3</b> </vlanId>	The VLAN ID to use for this VLAN. [Range = 2-4094.]
<ip> <b>10.250.55.0</b> </ip>	The network address of this VLAN [Range = A valid IP address]
<mask> <b>255.255.255.0</b> </mask>	Subnetting to apply to servers within this VLAN
<gateway> <b>10.250.55.1</b> </gateway>	The gateway router interface address associated with this network [Range = A valid IP address]
<isDefault>true</isDefault>	Indicates whether this is the network with a default gateway. [Range = true/false]
</network>	
<network>	

XML File Text	Description
<name>IMI</name>	Name of customer internal network. <b>Note:</b> Do NOT change this name.
<vlanId>4</vlanId>	The VLAN ID to use for this VLAN. [Range = 2-4094.]
<ip>169.254.100.0</ip>	The network address of this VLAN [Range = A valid IP address]
<mask>255.255.255.0</mask>	Subnetting to apply to servers within this VLAN
</network>	
</networks>	
</networkelement>	

Table 3. SDS XML SDS Network Element Configuration File (IPv6)

XML File Text	Description
<?xml version="1.0"?>	
<networkelement>	
<name>sds_mrsvnc</name>	Unique identifier used to label a Network Element. [Range = 1-32 character string. Valid characters are alphanumeric and underscore. Must contain at least one alpha and must not start with a digit.]
<ntpervers>	
</ntpervers>	
<networks>	
<network>	
<name>XMI</name>	Name of customer external network. <b>Note:</b> Do NOT change this name.
<vlanId>3</vlanId>	The VLAN ID to use for this VLAN. [Range = 2-4094.]
<ip>2606:b400:605:b804::</ip>	The network address of this VLAN [Range = A valid IP address]
<mask>/64</mask>	Subnetting to apply to servers within this VLAN
<gateway>2606:B400:605:B804:D27E:28FF:FEB3:4FE2</gateway>	The gateway router interface address associated with this network [Range = A valid IP address]

XML File Text	Description
<isDefault>true</isDefault>	Indicates whether this is the network with a default gateway. [Range = true/false]
</network>	
<network>	
<name>IMI</name>	Name of customer internal network. <b>Note:</b> Do NOT change this name.
<vlanId>4</vlanId>	The VLAN ID to use for this VLAN. [Range = 2-4094.]
<ip>FDBD:AAEC:587C:6EFB::</ip>	The network address of this VLAN [Range = A valid IP address]
<mask>/64</mask>	Subnetting to apply to servers within this VLAN
</network>	
</networks>	
</networkelement>	

## Appendix B. List of Frequently Used Time Zones

This table lists several valid time zone strings that can be used for the time zone setting in a CSV file, or as the time zone parameter when manually setting a DSR time zone.

**Table 4. List of Selected Time Zone Values**

<b>Time Zone Value</b>	<b>Description</b>	<b>Universal Time Code (UTC) Offset</b>
UTC	Universal Time Coordinated	UTC-00
America/New_York	Eastern Time	UTC-05
America/Chicago	Central Time	UTC-06
America/Denver	Mountain Time	UTC-07
America/Phoenix	Mountain Standard Time — Arizona	UTC-07
America/Los Angeles	Pacific Time	UTC-08
America/Anchorage	Alaska Time	UTC-09
Pacific/Honolulu	Hawaii	UTC-10
Africa/Johannesburg		UTC+02
America/Mexico City	Central Time — most locations	UTC-06
Africa/Monrovia		UTC+00
Asia/Tokyo		UTC+09
America/Jamaica		UTC-05
Europe/Rome		UTC+01
Asia/Hong Kong		UTC+08
Pacific/Guam		UTC+10
Europe/Athens		UTC+02
Europe/London		UTC+00
Europe/Paris		UTC+01
Europe/Madrid	mainland	UTC+01
Africa/Cairo		UTC+02
Europe/Copenhagen		UTC+01
Europe/Berlin		UTC+01
Europe/Prague		UTC+01
America/Vancouver	Pacific Time — west British Columbia	UTC-08
America/Edmonton	Mountain Time — Alberta, east British Columbia & west Saskatchewan	UTC-07
America/Toronto	Eastern Time — Ontario — most locations	UTC-05
America/Montreal	Eastern Time — Quebec — most locations	UTC-05
America/Sao Paulo	South & Southeast Brazil	UTC-03

<b>Time Zone Value</b>	<b>Description</b>	<b>Universal Time Code (UTC) Offset</b>
Europe/Brussels		UTC+01
Australia/Perth	Western Australia — most locations	UTC+08
Australia/Sydney	New South Wales — most locations	UTC+10
Asia/Seoul		UTC+09
Africa/Lagos		UTC+01
Europe/Warsaw		UTC+01
America/Puerto Rico		UTC-04
Europe/Moscow	Moscow+00 — west Russia	UTC+04
Asia/Manila		UTC+08
Atlantic/Reykjavik		UTC+00
Asia/Jerusalem		UTC+02



## Appendix C. Common KVM/OpenStack Tasks

### Appendix C.1 Import an OVA File

#### Procedure 21. Import and OVA File

Step	Procedure	Description
1. <input type="checkbox"/>	Create VM flavors	Use the [1] DSR Cloud Benchmarking Guide values to create flavors for each type of VM. Flavors can be created with the Horizon GUI in the <b>Admin</b> section, or with the <code>nova flavor-create</code> command line tool. Make the flavor names as informative as possible. As flavors describe resource sizing, a common convention is to use a name like "0406060" where the first two figures (04) represent the number of virtual CPUs, the next two figures (06) might represent the RAM allocation in GB, and the final three figures (060) might represent the disk space in GB.
2. <input type="checkbox"/>	Unpack and import an image file using the glance utility	<ol style="list-style-type: none"> <li>Copy the OVA file to the OpenStack control node. <pre>\$ scp SDS-x.x.x.ova admusr@node:~</pre></li> <li>Log into the OpenStack control node. <pre>\$ ssh admusr@node</pre></li> <li>In an empty directory unpack the OVA file using <b>tar</b> <pre>\$ tar xvf SDS-x.x.x.ova</pre></li> <li>One of the unpacked files will have a <b>.vmdk</b> suffix. This is the VM image file that must be imported.  SDS-8.6.x.x-disk1.vmdk</li> <li>Source the OpenStack <b>admin</b> user credentials. <pre>\$ . keystone_admin</pre></li> <li>Select an informative name for the new image.  sds-x.x.x-original</li> <li>Import the image using the <b>glance</b> utility from the command line. <pre>\$ glance image-create --name sds-x.x.x-original --visibility public --protected false --progress --container-format bare --disk-format vmdk --file SDS-x.x.x-disk1.vmdk</pre></li> </ol> <p>This process takes about 5 minutes depending on the underlying infrastructure.</p>

## Appendix C.2 Create a Network Port

### Procedure 22. Create a Network Port

Step	Procedure	Description
1. □	Create the network ports for the NO network interfaces	<p>1. Each network interface on an instance must have an associated network port.</p> <p>An instance usually has at least eth0 and eth1 for a public and private network respectively.</p> <p>Some configurations require 6 or more interfaces and corresponding network ports.</p> <p>2. Determine the IP address for the interface.</p> <p>For eth0, the IP might be 10.x.x.157. For eth1, the IP might be 192.168.x.157</p> <p>3. Identify the neutron network ID associated with each IP/interface using the <b>neutron</b> command line tool.</p> <pre>\$ neutron net-list</pre> <p>4. Identify the neutron subnet ID associated with each IP/interface using the <b>neutron</b> command line tool.</p> <pre>\$ neutron subnet-list</pre> <p>5. Create the network port using the <b>neutron</b> command line tool, being sure to choose an informative name. Note the use of the subnet ID and the network ID (final argument).</p> <p>Port names are usually a combination of instance name and network name.</p> <p>NOAM-A-xmi SO2-imi MP5-xsi2</p> <p>The ports must be owned by the DSR tenant user, not the admin user. Either source the credentials of the DSR tenant user or use the DSR tenant user ID as the value for the <b>—tenant-id</b> argument.</p> <pre>\$ . keystone_rc_dsr_user \$ keystone user-list \$ neutron port-create --name=NO1-xmi --tenant-id &lt;tenant id&gt; --fixed-ip subnet_id=&lt;subnet id&gt;,ip_address=10.x.x.157 &lt;network id&gt; \$ neutron port-create --name=NO1-imi --tenant-id &lt;tenant id&gt; --fixed-ip subnet_id=&lt;subnet id&gt;,ip_address=192.168.x.157 &lt;network id&gt;</pre> <p>View your newly created ports using the neutron tool.</p> <pre>\$ neutron port-list</pre>

## Appendix C.3 Create and Boot OpenStack Instance

### Procedure 23. Create and Boot OpenStack Instance

Step	Procedure	Description
1. □	Create a VM instance from a glance image	<p>1. Get the following configuration values.</p> <p>The image ID.</p> <pre>\$ glance image-list</pre> <p>The flavor ID.</p> <pre>\$ nova flavor-list</pre> <p>The network ID(s)</p> <pre>\$ neutron net-list</pre> <p>An informative name for the instance.</p> <p>NOAM-A SO2 MP5</p> <p>2. Create and boot the VM instance.</p> <p>The instance must be owned by the DSR tenant user, not the admin user. Source the credentials of the DSR tenant user and issue the following command.</p> <p><b>Note:</b> IPv6 addresses should use the <b>v6-fixed-ip</b> argument instead of <b>v4-fixed-ip</b>.</p> <pre>\$ nova boot --image &lt;image ID&gt; --flavor &lt;flavor id&gt; --nic net-id=&lt;first network id&gt;,v4-fixed-ip=&lt;first ip address&gt; --nic net-id=&lt;second network id&gt;,v4-fixed-ip=&lt;second ip address&gt; InstanceName</pre> <p>View the newly created instance using the nova tool.</p> <pre>\$ nova list --all-tenants</pre> <p>The VM takes approximately 5 minutes to boot. At this point, the VM has no configured network interfaces and can only be accessed by the Horizon console tool.</p>

## Appendix C.4 Configure Networking for OpenStack Instance

### Procedure 24. Configure Networking for OpenStack Instance

Step	Procedure	Description
1. <input type="checkbox"/>	Verify/Configure the network interface	<ol style="list-style-type: none"> <li>1. Check if the interface is configured automatically.</li> <li>2. If DHCP is enabled on Neutron subnet, VM configures the VNIC with the IP address. To verify, ping the XMI IP address provided with the <b>nova boot</b> command: <pre>\$ping &lt;XMI-IP-Provided-During-Nova-Boot&gt;</pre> <p>If the ping is successful, ignore the next part to configure the interface manually.</p> <p>Manually configure the interface, if not already done (optional).</p> <ol style="list-style-type: none"> <li>a. Log into the Horizon GUI as the DSR tenant user.</li> <li>b. Go to the Compute/Instances section.</li> <li>c. Click on the Name field of the newly created instance.</li> <li>d. Select the Console tab.</li> <li>e. Login as the admusr user.</li> <li>f. Configure the network interfaces, conforming with the OCDSR Network to Device Assignments in defined Appendix A Create an XML file for Installing SDS Network Elements. <pre>\$ sudo netAdm add --onboot=yes --device=eth0 --address=&lt;xmi ip&gt; --netmask=&lt;xmi net mask&gt;</pre> <pre>\$ sudo netAdm add --route=default --device=eth0 --gateway=&lt;xmi gateway ip&gt;</pre> <p>Under some circumstances, it may be necessary to configure as many as 6 or more interfaces.</p> <p>If netAdm fails to create the new interface (ethX) because it already exists in a partially configured state, perform the following actions.</p> <pre>\$ cd /etc/sysconfig/network-scripts</pre> <pre>\$ sudo mv ifcfg-ethX /tmp</pre> <p>Re-run the netAdm command. It will create and configure the interface in one action.</p> </li> </ol> </li> <li>3. Reboot the VM. It takes approximately 5 minutes for the VM to complete rebooting. <pre>\$ sudo init 6</pre> <p>The new VM should now be accessible using both network and Horizon console.</p> </li> </ol>

## Appendix D. Application VIP Failover Options (OpenStack)


### Appendix D.1 Application VIP Failover Options

Within an OpenStack cloud environment, there are several options for allowing applications to manage their own virtual IP (VIP) addresses as is traditionally done in telecommunications applications. This document describes two of those options:

- Allowed address pairs
- Disable port security

Each of these options is covered in the major sub-sections that follow. The last major sub-section discusses how to utilize application managed virtual IP addresses within an OpenStack VM instance.

Both of these options effectively work around the default OpenStack Networking (Neutron) service anti-spoofing rules that ensure that a VM instance cannot send packets out a network interface with a source IP address different from the IP address Neutron has associated with the interface. In the Neutron data model, the logical notion of networks, sub-networks and network interfaces are realized as networks, subnets, and ports as shown in Figure 1:



**Figure 1. Neutron High-Level Data Model**

Note how a port in the Neutron data model maps to at most one VM instance where internal to the VM instance, the port is represented as an available network device such as eth0. VM instances can have multiple network interfaces in which case there are multiple Neutron ports associated with the VM instance, each with different MAC and IP addresses.

Each Neutron port by default has one MAC Address and one IPv4 or IPv6 address associated with it. The IP address associated with a port can be assigned in two ways:

- Automatically by Neutron when creating a port to fulfill an OpenStack Compute (Nova) service request to associate a network interface with a VM instance to be instantiated OR
- Manually by a cloud administrator when creating or updating a Neutron port

The anti-spoofing rules are enforced at the Neutron port level by ensuring that the source IP address of outgoing packets matches the IP address Neutron has associated with the corresponding port assigned to the VM instance. By default if the source IP address in the outgoing packet does not match the IP address associated with the corresponding Neutron port then the packet is dropped.

These anti-spoofing rules clearly create a complication for the use of application managed virtual IP addresses since Neutron is not going to know about the VIPs being applied by the application to VM instance network interfaces without some interaction between the application (or a higher level management element) and Neutron. Which is why the two options in this document either fully disable the port security measures within Neutron, including the anti-spoofing rules, or expand the set of allowable source IP addresses to include the VIPs that may be used by the application running within a VM instance.

Note that for both of the options described in the following sub-sections, there is a particular Neutron service extension or feature that must be enabled for the option to work. For one option (allowed address pairs) the required Neutron extension is enabled in most default deployments whereas for the other option (allow port security to be disabled) it is not.

Within this document when describing how to use either of these two options, there is example command line operations that interact with the OpenStack Neutron service using its command line utility, simply named `neutron`. However, be aware that all of the operations performed using the `neutron` command line utility can also be performed through the Neutron REST APIs, see the [Networking v2.0 API documentation](#) for more information.

## Appendix D.2 Allowed Address Pairs

This section describes an option that extends the set of source IP addresses that can be used in packets being sent out a VM instance's network interface (which maps to a Neutron port). This option utilizes a Neutron capability, called the allowed-address-pairs extension, which allows an entity (cloud administrator, management element, etc.) to define additional IP addresses to be associated with a Neutron port. In this way, if an application within the VM instance sends an outgoing packet with one of those additional IP addresses, then Neutron anti-spoofing rules enforcement logic does not drop those packets. The Neutron allowed-address-pairs extension is available starting with the OpenStack Havana release.

The three sub-sections that follow describe the OpenStack configuration requirements for this option, how to use this option after a VM instance has already booted, and how to utilize this option before a VM instance has booted.

## Appendix D.3 OpenStack Configuration Requirements

The Neutron allowed-address-pairs extension needs to be enabled for this option to work. For most OpenStack cloud deployments this extension should be enabled by default but to check, run the following command (after sourcing the appropriate user credentials file):

```
# neutron ext-list
+-----+-----+
| alias           | name           |
+-----+-----+
| security-group  | security-group |
| l3_agent_scheduler | L3 Agent Scheduler |
| net-mtu         | Network MTU    |
| ext-gw-mode     | Neutron L3 Configurable external gateway mode |
| binding         | Port Binding   |
| provider        | Provider Network |
| agent           | agent          |
| quotas          | Quota management support |
| subnet_allocation | Subnet Allocation |
| dhcp_agent_scheduler | DHCP Agent Scheduler |
| l3-ha           | HA Router extension |
| multi-provider  | Multi Provider Network |
| external-net    | Neutron external network |
| router          | Neutron L3 Router |
| allowed-address-pairs | Allowed Address Pairs |
| extraroute      | Neutron Extra Route |
| extra_dhcp_opt  | Neutron Extra DHCP opts |
| dvr             | Distributed Virtual Router |
+-----+-----+
```

The allowed-address-pairs extension should appear in the list of extensions as shown in the highlighted line.

## Appendix D.4 After a VM Instance has been Booted: Allowed Address Pairs

If a VM instance has already been booted, that is, instantiated, and you need to associate one or more additional IP addresses with the Neutron port assigned to the VM instance then you need to execute a command of the following form:

```
# neutron port-update <Port ID> --allowed_address_pairs list=true type=dict ip_address=<VIP address to be added>
```

where the bolded items have the following meaning:

- **<Port ID>**  
Identifies the ID of the port within Neutron which can be determined by listing the ports, `neutron port-list`, or if the port is named then the port ID can be obtained directly in the above command with a sequence like `$(neutron port-show -f value -F id <Port Name>)` to replace the `<Port ID>` placeholder.
- **<VIP address to be added>**  
Identifies the IP address, a virtual IP address in this case, that should additionally be associated with the port where this can be a single IP address, for example, 10.133.97.135/32, or a range of IP addresses as indicated by a value such as 10.133.97.128/30.

So for example if you wanted to indicate to Neutron that the allowed addresses for a port should include the range of addresses between 10.133.97.136 to 10.133.97.139 and the port had an ID of 8a440d3f-4e5c-4ba2-9e5e-7fc94211277 then you would type the following command:

```
# neutron port-update 8a440d3f-4e5c-4ba2-9e5e-7fc942111277 --
allowed_address_pairs list=true type=dict ip_address=10.133.97.136/30
```

## Appendix D.5 Before a VM Instance has been Booted: Allowed Address Pairs

If you want to associate additional allowed IP addresses with a port before it is associated with a VM instance then you need to first create the port and then associate one or more ports with a VM instance when it is booted. The command to create a new port with defined allowed address pairs is of the following form:

```
# neutron port-create --name <Port Name> --fixed-ip subnet-id=$(neutron
subnet-show -f value -F id <Subnet name>),ip_address=<Target IP address>
$(neutron net-show -f value -F id <Network name>) --allowed_address_pairs
list=true type=dict ip_address=<VIP address to be added>
```

where the bolded items have the following meaning:

- **<Port Name>**  
This is effectively a string alias for the port that is useful when trying to locate the ID for the port but the **--name <Port Name>** portion of the command is completely optional.
- **<Subnet name>**  
The name of the subnet to which the port should be added.
- **<Target IP address>**  
The unique IP address to be associated with the port.
- **<Network Name>**  
The name of the network with which the port should be associated.
- **<VIP address to be added>**  
This parameter value has the same meaning as described in the previous section.

So for example if you wanted to indicate to Neutron that a new port should have an IP address of 10.133.97.133 on the **ext-subnet** subnet with a single allowed address pair, 10.133.97.134, then you would type a command similar to the following:

```
# neutron port-create -name foo --fixed-ip subnet-id=$(neutron subnet-show -f
value -F id ext-subnet),ip_address=10.133.97.133 $(neutron net-show -f value
-F id ext-net) --allowed_address_pairs list=true type=dict
ip_address=10.133.97.134/32
```

Once the port or ports with the additional allowed addresses have been created, when you boot the VM instance use a nova boot command similar to the following:

```
# nova boot --flavor m1.xlarge --image testVMimage --nic port-id=$(neutron
port-show -f value -F id <Port Name>) testvm3
```

where the flavor, image, and VM instance name values need to be replaced by values appropriate for your VM. If the port to be associated with the VM instance is not named, then you need to obtain the port's ID using the neutron port-list command and replace the `$(neutron port-show -f value -F id <Port Name>)` sequence in the above command with the port's ID value.



## Appendix D.6 Disable Port Security

This section describes an option that rather than extending the set of source IP addresses that are associated with a Neutron port, as is done with the allowed-address-pairs extension, to disable the Neutron anti-spoofing filter rules for a given port. This option allows all IP packets originating from the VM instance to be propagated no matter whether the source IP address in the packet matches the IP address associated with the Neutron port or not. This option relies upon the Neutron port security extension that is available starting with the OpenStack Kilo release.

### OpenStack Configuration Requirements

The Neutron port security extension needs to be enabled for this method to work. For the procedure to enable the port security extension see:

[ML2 Port Security Extension Wiki page](#)

**Note:** Enabling the port security extension when there are already existing networks within the OpenStack cloud causes all network related requests into Neutron to fail due to a [known bug in Neutron](#). There is a fix identified for this bug that is part of the Liberty release and is scheduled to be backported to the Kilo 2015.1.2 release. In the meantime, **this option is only non-disruptive when working with a new cloud deployment where the cloud administrator can enable this feature before any networks and VM instances that use those networks are created.** The port security extension can be enabled in an already deployed OpenStack cloud, but all existing networks, subnets, ports, etc., need to be deleted before enabling the port security extension. This typically means all VM instances also need to be deleted as well, but a knowledgeable cloud administrator **may** be able to do the following to limit the disruption of enabling the port security extension:

- Record the current IP address assignments for all VM instances,
- Remove the network interfaces from any existing VM instances,
- Delete the Neutron resources,
- Enable the port security extension,
- Re-create the previously defined Neutron resources (networks, subnets, ports, etc.), and then
- Re-add the appropriate network interfaces to the VMs.

Depending on the number of VM instances running in the cloud, this procedure may or may not be practical.

## Appendix D.7 After a VM Instance has been Booted: Port Security

If you need to disable port security for a port after it has already been associated with a VM instance, then you need to execute one or both of the following commands to use the port security option. First, if the VM instance with which the existing port is associated has any associated security groups (`run nova list-secgroup <VM instance name>` to check), then you first need to run a command of the following form for each of the security group(s) associated with the VM instance:

```
# nova remove-secgroup <VM instance name> <Security group name>
```

where the bolded item has the following meaning:

- **<VM instance name>**  
Identifies the name of the VM instance for which the identified security group name should be deleted.
- **<Security group name>**  
Identifies the name of the security group that should be removed from the VM instance.

So for example if you wanted to remove the default security group from a VM instance named 'testvm4' then you would type a command similar to the following:

```
# nova remove-secgroup testvm4 default
```

Once any security groups associated with VM instance to which the Neutron port is assigned have been removed, then the Neutron port(s) associated with the target VM instance need to be updated to disable port security on those ports. The command to disable port security for a specific Neutron port is of the form:

```
# neutron port-update <Port ID> -- port-security-enabled=false
```

where the bolded item has the following meaning:

- **<Port ID>**  
Identifies the ID of the port within Neutron which can be determined by listing the ports, `neutron port-list`, or if the port is named then the port ID can be obtained directly in the above command with a sequence such as `$(neutron port-show -f value -F id <Port Name>)`.

So for example if you wanted to indicate to Neutron that port security should be disabled for a port with an ID of 6d48b5f2-d185-4768-b5a4-c0d1d8075e41 then you would type the following command:

```
# neutron port-update 6d48b5f2-d185-4768-b5a4-c0d1d8075e41 --port-security-enabled=false
```

If the port-update command succeeds, within the VM instance with which the 6d48b5f2-d185-4768-b5a4-c0d1d8075e41 port is associated, application managed VIPs can now be added to the network interface within the VM instance associated with the port and network traffic using that VIP address should now propagate.

## Appendix D.8 Before a VM Instance has been Booted: Port Security

If you want to disable port security for a port before it is associated with a VM instance, then you need to first create the port at which time you can specify that port security should be disabled. The command to create a new port with port security disabled is of the following form:

```
# neutron port-create --name <Port Name> --port-security-enabled=false --fixed-ip subnet-id=$(neutron subnet-show -f value -F id <Subnet name>),ip_address=<Target IP address> $(neutron net-show -f value -F id <Network name>)
```

where the bolded items have the following meaning:

- **<Port Name>**  
This is effectively a string alias for the port that is useful when trying to locate the ID for the port but the **--name <Port Name>** portion of the command is completely optional.
- **<Subnet name>**  
The name of the subnet to which the port should be added.
- **<Target IP address>**  
The unique IP address to be associated with the port.
- **<Network Name>**  
The name of the network with which the port should be associated.

So for example if you wanted to indicate to Neutron that a new port should have port security disabled and an IP address of 10.133.97.133 on the **ext-subnet** subnet then you would type a command similar to the following:

```
# neutron port-create -name foo --port-security-enabled=false --fixed-ip
subnet-id=$(neutron subnet-show -f value -F id ext-
subnet),ip_address=10.133.97.133 $(neutron net-show -f value -F id ext-net)
```

Once the port or ports with port security disabled have been created, when you boot the VM instance, you need to execute a command similar to the following:

```
# nova boot --flavor m1.xlarge --image testVMimage --nic port-id=$(neutron
port-show -f value -F id <Port Name>) testvm3
```

where the flavor, image, and VM instance name values need to be replaced by values appropriate for your VM. If the port to be associated with the VM instance is not named, then you need to obtain the port's ID using the `neutron port-list` command and replace the `$(neutron port-show -f value -F id <Port Name>)` sequence in the above command with the port's ID value.

## Appendix D.9 Managing Application Virtual IP Addresses within VM Instances

Once either of the previously described options is in place to enable applications to manage their own virtual IP addresses, there should be no modifications required to how the application already manages its VIPs in a non-virtualized configuration. There are many ways that an application can add or remove virtual IP addresses but as a reference point, here are some example command line operations to add a virtual IP address of 10.133.97.136 to the eth0 network interface within a VM and then send four gratuitous ARP packets to refresh the ARP caches of any neighboring nodes:

```
# ip address add 10.133.97.136/23 broadcast 10.133.97.255 dev eth0 scope
global
# arping -c 4 -U -I eth0 10.133.97.136
```

As the creation of virtual IP addresses typically coincides with when an application is assigned an active role, the above operations would be performed both when an application instance first receives an initial active HA role or when an application instance transitions from a standby HA role to the active HA role.

## Appendix E. Common OVM-Manager Tasks (CLI)

### Appendix E.1 Set Up the Server

**Note:** This section sets up the server using the command line interface of OVM Manager. All configurations/setup **can also be done** from the GUI/dashboard of OVM Manager.

#### Procedure 25. Set Up the Server

Step	Procedure	Description
1. <input type="checkbox"/>	Log into the OVM-M command line interface	<pre>ssh -l admin &lt;OVM-M IP&gt; -p 1000</pre> <p>Example:</p> <pre>[root@manager01 ~]# ssh -l admin 10.240.16.138 -p 10000 admin@10.240.16.138's password:</pre>
2. <input type="checkbox"/>	<b>OVM-M CLI:</b> Discover Oracle VM server	<pre>discoverServer ipAddress=value password=value takeOwnership= { Yes   No }</pre> <p>Example:</p> <pre>OVM&gt;discoverServer ipAddress=10.240.16.139 password=password takeOwnership=Yes</pre>
3. <input type="checkbox"/>	<b>OVM-M CLI:</b> Create an ethernet-based network with the VM role	<pre>create Network [ roles= { MANAGEMENT   LIVE_MIGRATE   CLUSTER_HEARTBEAT   VIRTUAL_MACHINE   STORAGE } ] name=value [ description=value ] [ on Server instance ]</pre> <p>Example:</p> <pre>OVM&gt;create Network name=XMI roles=VIRTUAL_MACHINE</pre>
4. <input type="checkbox"/>	<b>OVM-M CLI:</b> Add a port from each Oracle VM server to the network	<p><b>Note:</b> Skip this step and proceed to step 5 for bonded interfaces.</p> <ol style="list-style-type: none"> <li>Find the ID of an Ethernet port. <pre>OVM&gt; show Server name=MyServer1 ... Ethernet Port 1 = 0004fb00002000007711332ff75857ee [eth0 on MyServer3.virtlab.info] Ethernet Port 2 = 0004fb0000200000d2e7d2d352a6654e [eth1 on MyServer3.virtlab.info] Ethernet Port 3 = 0004fb0000200000c12192a08f2236e4 [eth2 on MyServer3.virtlab.info]</pre> </li> <li>Add a port from each Oracle VM Server to the network. <pre>OVM&gt;add Port instance to { BondPort   Network } instance</pre> <p>Example:</p> <pre>OVM&gt;add Port id=0004fb0000200000d2e7d2d352a6654e to Network name=MyVMNetwork</pre> </li> </ol>

**Procedure 25. Set Up the Server**

Step	Procedure	Description
5. <input type="checkbox"/>	<b>OVM-M CLI:</b> Create Bondport (For Bonded Interfaces)	<p>1. Find the ID of an Ethernet port.</p> <pre>OVM&gt;list Port Status: Success Time: 2016-08-22 04:43:02,565 EDT Data: id:0004fb000020000045b4e8dc0b3acc6 name:usb0 on vms01.test.com id:0004fb00002000005fde208ce6392c0a name:eth4 on vms01.test.com id:0004fb0000200000b1dceeb39006d839 name:eth5 on vms01.test.com id:0004fb000020000027e3a02bc28dd153 name:eth2 on vms01.test.com id:0004fb0000200000fce443e0d30cd3d5 name:eth3 on vms01.test.com id:0004fb0000200000a908e402fc542312 name:eth0 on vms01.test.com id:0004fb0000200000247b03c2a4a090ec name:eth1 on vms01.test.com</pre> <p>2. Create Bondport on required interfaces.</p> <pre>OVM&gt;create BondPort ethernetPorts="0004fb0000200000b1dceeb39006d839,0004fb0000200000fce443e0d30cd3d5" mode=ACTIVE_PASSIVE mtu=1500 name=bond1 on Server name=compute01.test.com  Command: create BondPort ethernetPorts="0004fb0000200000b1dceeb39006d839,0004fb0000200000fce443e0d30cd3d5" mode=ACTIVE_PASSIVE mtu=1500 name=bond1 on Server name=compute01.test.com Status: Success</pre>
6. <input type="checkbox"/>	<b>OVM-M CLI:</b> Add VLAN Interface to network (for VLAN tagged networks)	<p>1. Find the ID of an Ethernet port.</p> <pre>OVM&gt;list BondPort Command: list BondPort Status: Success Time: 2016-08-22 04:38:22,327 EDT Data: id:0004fb00002000005a45a0761813d512 name:bond1 id:0004fb0000200000645cfc865736cea8 name:bond0 on compute01.test.com</pre> <p>2. Create VLAN interface.</p>

**Procedure 25. Set Up the Server**

Step	Procedure	Description
		<pre>OVM&gt;create VlanInterface vlanId=43 name=bond1.43 on BondPort id=0004fb00002000005a45a0761813d512  Command: create VlanInterface vlanId=43 name=bond1.43 on BondPort id=0004fb00002000005a45a0761813d512  Status: Success</pre> <p><b>3. Add remaining VLAN interfaces to the same bond accordingly, like:</b></p> <pre>OVM&gt;create VlanInterface vlanId=44 name=bond1.44 on BondPort id=0004fb00002000005a45a0761813d512  OVM&gt;create VlanInterface vlanId=30 name=bond1.30 on BondPort id=0004fb00002000005a45a0761813d512  OVM&gt;create VlanInterface vlanId=31 name=bond1.31 on BondPort id=0004fb00002000005a45a0761813d512</pre> <p><b>4. Add VLAN interfaces to network.</b></p> <pre>OVM&gt;add VlanInterface name=bond1.43 to Network name=XMI  Command: add VlanInterface name=bond1.43 to Network name=XMI  Status: Success  Time: 2016-08-22 05:14:29,321 EDT  JobId: 1471857258238  OVM&gt;add VlanInterface name=bond1.44 to Network name=IMI  Command: add VlanInterface name=bond1.44 to Network name=IMI  Status: Success  Time: 2016-08-22 05:15:24,216 EDT  JobId: 1471857321329  OVM&gt;add VlanInterface name=bond1.30 to Network name=XSI1  Command: add VlanInterface name=bond1.30 to Network name=XSI1  Status: Success  Time: 2016-08-22 05:15:39,190 EDT  JobId: 1471857337005  OVM&gt;add VlanInterface name=bond1.31 to Network name=XSI2  Command: add VlanInterface name=bond1.31 to Network name=XSI2  Status: Success  Time: 2016-08-22 05:15:52,576 EDT</pre>

**Procedure 25. Set Up the Server**

Step	Procedure	Description
		JobId: 1471857349684
7. <input type="checkbox"/>	<b>OVM-M CLI:</b> Create unclustered server pool	<b>Note:</b> To create clustered server pool, ignore this step and proceed to next.  OVM>create ServerPool clusterEnable=No name=MyServerPool description='Unclustered server pool'
8. <input type="checkbox"/>	<b>OVM-M CLI:</b> Create clustered server pool (Optional)	<b>Note:</b> Skip this step if an unclustered server pool is already created. This step is only if required to create a clustered server pool.  1. To create a clustered server pool you must provide a file system or physical disk to use for the server pool file system. To find a file system or physical disk, use the list command:  OVM>list FileSystem  id:66a61958-e61a-44fe-b0e0-9dd64abef7e3 name:nfs on 10.172.76.125:/mnt/vol1/poolfs03  id:0004fb0000050000b85745f78b0c4b61 name:fs on 350014ee2568cc0cf  id:4ebb1575-e611-4662-87b9-a84b40ce3db7 name:nfs on 10.172.76.125:/mnt/vol1/poolfs04  id:858d98c5-3d8b-460e-9160-3415cbdda738 name:nfs on 10.172.76.125:/mnt/vol1/poolfs01  id:0dea4818-20e6-4d3a-958b-b12cf91588b5 name:nfs on 10.172.76.125:/mnt/vol1/poolfs02  id:35b4f1c6-182b-4ea5-9746-51393f3b515c name:nfs on 10.172.76.125:/mnt/vol2/repo03  id:aeb6143d-0a96-4845-9690-740bbf1e225e name:nfs on 10.172.76.125:/mnt/vol1/repo01  id:05e8536f-8d9c-4d7c-bbb2-29b3ffafe011 name:nfs on 10.172.76.125:/mnt/vol2/repo02  id:0004fb00000500006a46a8dbd2461939 name:MyServerPool_cluster_heartbeat  id:0004fb00000500000809e28f4fab56b1 name:fs on 350014ee20137ee44  OVM>list PhysicalDisk  id:0004fb000018000019b86ccf3f473a9e name:FreeBSD (9) id:0004fb0000180000c4609a67d55b5803 name:FreeBSD (3)  id:0004fb00001800002179de6afe5f0cf3 name:SATA_WDC_WD5001ABYS-_WD-WCAS86288968  id:0004fb0000180000a0b43f9684fc78ac name:FreeBSD (2) id:0004fb0000180000732be086afb26911 name:FreeBSD (7) id:0004fb000018000067ce80973e18374e name:FreeBSD (8) id:0004fb000018000035ce16ee4d58dc4d name:FreeBSD (1)

**Procedure 25. Set Up the Server**

Step	Procedure	Description
		<pre>id:0004fb00001800006855117242d9a537 name:FreeBSD (6) id:0004fb0000180000a9c7a87ba52ce5ec name:FreeBSD (5) id:0004fb0000180000ebabef9838188d78 name:SATA_WDC_WD5001ABYS-_WD-WCAS86571931 id:0004fb00001800008f6ea92426f2cfb8 name:SATA_WDC_WD5001ABYS-_WD-WCAS86257005 id:0004fb00001800008ccb1925cdbbd181 name:SATA_WDC_WD5001ABYS-_WD-WCAS86578538 id:0004fb0000180000e034b4662665161c name:FreeBSD (4)</pre> <p>2. Before you create a clustered server pool you must refresh the file system or physical disk to be used for the server pool file system. To refresh a file system:</p> <pre>OVM&gt;refresh { AccessGroup   Assembly   FileServer   FileSystem   PhysicalDisk   Repository   Server   StorageArray   VirtualAppliance } instance</pre> <p>For example, to refresh a physical disk:</p> <pre>OVM&gt;refresh PhysicalDisk id=0004fb000018000035ce16ee4d58dc4d</pre> <p>3. Refresh a file system:</p> <pre>OVM&gt;refresh FileSystem name="nfs on 10.172.76.125://mnt//vol1//repo01"</pre> <pre>OVM&gt;create ServerPool clusterEnable=Yes filesystem="nfs on 10.172.76.125://mnt//vol1//poolfs01" name=MyServerPool description='Clustered server pool'</pre>
9. <input type="checkbox"/>	<b>OVM-M CLI:</b> Add Oracle VM servers to the server pool	<pre>OVM&gt;add Server name=MyServer to ServerPool name=MyServerPool</pre>
10. <input type="checkbox"/>	<b>OVM-M CLI:</b> Create storage repository	<p>1. Find the physical disk (LUN) to use for creating the storage repository.</p> <pre>OVM&gt;list FileServer Command: list FileServer Status: Success Time: 2016-08-19 02:11:39,779 EDT Data: id:0004fb00000900000445dac29e88bc38 name:Local FS vms03.test.com id:0004fb0000090000045715cad6f165ecf name:Local FS vms01.test.com</pre>



**Procedure 25. Set Up the Server**

Step	Procedure	Description
		<pre> id:0004fb0000090000df4cd9c3170092e4  name:Local FS vms02.test.com  id:0004fb000009000064b96ed88a9a0185  name:Local FS vms04.test.com  2. Find a local file system on an Oracle VM server that has access to the LUN.  OVM&gt;list FileServer  Command: list FileServer  Status: Success  Time: 2016-08-19 02:11:39,779 EDT  Data:  id:0004fb00000900000445dac29e88bc38  name:Local FS vms03.test.com  id:0004fb000009000045715cad6f165ecf  name:Local FS vms01.test.com  id:0004fb0000090000df4cd9c3170092e4  name:Local FS vms02.test.com  id:0004fb000009000064b96ed88a9a0185  name:Local FS vms04.test.com  3. Create file system.  OVM&gt;create FileSystem name=VmsFs01 physicalDisk="OVM_SYS_REPO_PART_3600605b00a2a024000163e 490ac3f392" on FileServer name="Local FS vms01.test.com"  Command: create FileSystem name=VmsFs01 physicalDisk="OVM_SYS_REPO_PART_3600605b00a2a024000163e 490ac3f392" on FileServer name="Local FS vms01.test.com"  Status: Success  Time: 2016-08-19 02:22:46,581 EDT  JobId: 1471587738752  Data:  id:0004fb00000500006779d42da60c0be6  name:VmsFs01  4. Create repository.  OVM&gt;create Repository name=Vms01Repo on FileSystem name=VmsFs01  Command: create Repository name=Vms01Repo on FileSystem name=VmsFs01  Status: Success  Time: 2016-08-19 02:24:04,092 EDT </pre>

**Procedure 25. Set Up the Server**

Step	Procedure	Description
		<pre> JobId: 1471587843432  Data:  id:0004fb00000300003c8f771791114d53  name:Vms01Repo  5. Add server pool to repository.  OVM&gt; add ServerPool name=TestPool001 to Repository name=Vms01Repo  Refresh the storage repository using the syntax:  OVM&gt; refresh Repository name=MyRepository </pre>

**Appendix E.2 Server Pool**

A server pool is a required entity in Oracle VM, even if it contains a single Oracle VM Server. In practice, several Oracle VM servers form a server pool, and an Oracle VM environment may contain one or several server pools. Server pools are typically clustered, although an unclustered server pool is also possible. Server pools have shared access to storage repositories and exchange and store vital cluster information in the server pool file system. Refer [2] Oracle VM Concepts Guide, E64081-09, Release 3.4 for more information.

## Appendix F. My Oracle Support (MOS)

MOS (<https://support.oracle.com>) is your initial point of contact for all product support and training needs. A representative at Customer Access Support (CAS) can assist you with MOS registration.

Call the CAS main number at **1-800-223-1711** (toll-free in the US), or call the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. When calling, make the selections in the sequence shown below on the Support telephone menu:

1. Select **2** for New Service Request.
2. Select **3** for Hardware, Networking, and Solaris Operating System Support.
3. Select one of the following options:

For technical issues such as creating a new Service Request (SR), select **1**.

For non-technical issues such as registration or assistance with MOS, select **2**.

You are connected to a live agent who can assist you with MOS registration and opening a support ticket. MOS is available 24 hours a day, 7 days a week, 365 days a year.

## Appendix G. Emergency Response

In the event of a critical service situation, emergency response is offered by the CAS main number at 1-800-223-1711 (toll-free in the US), or by calling the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. The emergency response provides immediate coverage, automatic escalation, and other features to ensure that the critical situation is resolved as rapidly as possible.

A critical situation is defined as a problem with the installed equipment that severely affects service, traffic, or maintenance capabilities, and requires immediate corrective action. Critical situations affect service and/or system operation resulting in one or several of these situations:

- A total system failure that results in loss of all transaction processing capability
- Significant reduction in system capacity or traffic handling capability
- Loss of the system's ability to perform automatic system reconfiguration
- Inability to restart a processor or the system
- Corruption of system databases that requires service affecting corrective actions
- Loss of access for maintenance or recovery operations
- Loss of the system ability to provide any required critical or major trouble notification

Any other problem severely affecting service, capacity/traffic, billing, and maintenance capabilities may be defined as critical by prior discussion and agreement with Oracle.

## Appendix H. Locate Product Documentation on the Oracle Help Center

Oracle Communications customer documentation is available on the web at the Oracle Help Center (OHC) site, <http://docs.oracle.com>. You do not have to register to access these documents. Viewing these files requires Adobe Acrobat Reader, which can be downloaded at <http://www.adobe.com>.

1. Access the **Oracle Help Center** site at <http://docs.oracle.com>.
2. Click **Industries**.
3. Under the **Oracle Communications** subheading, click the **Oracle Communications documentation** link. The Communications Documentation page appears. Most products covered by these documentation sets display under the headings **Network Session Delivery and Control Infrastructure** or **Platforms**.
4. Click on your Product and then the Release Number. A list of the entire documentation set for the selected product and release displays.
5. To download a file to your location, right-click the PDF link, select `Save target as` (or similar command based on your browser), and save to a local folder.