Installer Database Setup Oracle Banking Trade Finance Release 14.7.0.0.0 Part No. F74393-01

[November] [2022]



Table of Contents

1.	INS'	TALLING ORACLE BANKING TRADE FINANCE DATABASE	1-1
1	.1	INTRODUCTION CREATING SCHEMA BY IMPORTING FULL DUMP	1-1
	.3	CREATING SCHEMA FROM SHIPMENT MEDIA	1-1
	1.3.1 1.3.2	1 Backend Setup using Silent Installer 2 Basic Setup using GUI Installer	1-1 1-2



1. Installing Oracle Banking Trade Finance Database

1.1 Introduction

Oracle Banking Trade Finance database can be installed in one of the following methods.

- Import full dump Import the Oracle Banking Trade Finance objects into an empty schema using full dump. This is a manual activity.
- From shipment media Load the shipment media objects into an empty schema using Installer.

These methods are discussed in detail under the following heads.

1.2 Creating Schema by Importing Full Dump

Under this method, you need to manually import the Oracle Banking Trade Finance DMP file into the Oracle Banking Trade Finance schema. This can be done using the following command:

\$impdp user_name/password directory=dir_name dumpfile=dmp_file_name.dmp logfile=dmp_file_name.log remap_schema=from_schema_name:to_schema_name remap_tablespace=from_tablespace_name:to_tablespace_name transform=OID:n

1.3 Creating Schema from Shipment Media

Under this method, you need to create the schema from the shipment media.

1.3.1 Backend Setup using Silent Installer

Backend Setup has to be done using Silent Installer. DDL Compilation, Object Compilation and Static Data Load will be taken care as part of Backend Setup.

Before loading objects into the schema, fcubs.properties file creation must be performed with the required database details using the GUI installer (Refer OBTF_Installer_Property_File_Creation document). After the property file is created, env.properties file, present in INSTALLER/SOFT/GUI/logs/ directory, will be automatically updated, with the details provided while creating the property file.

env.properties file present in INSTALLER/SOFT/GUI/logs/ will be automatically copied to INSTALLER/SOFT/logs/ directory as part of property file creation. Details from this env.properties are taken for further steps.

Run the **<Product Processor>**DBCompileRun.bat from INSTALLER/SOFT directory. DDL Compilation, Object Compilation and Static Data load will be done.

For Example: OBTF INSTALLATION-

First load SMS objects first and then OBTF objects. i.e.



- a. Run SMSDBCompileRun.bat in windows (SMSDBCompileRun.sh in linux). Note: Before running DB Compilation of any sort, please make sure that System Date Time format and language are provided as English, or otherwise DB Compilation might fail due to improper log names.
- b. After SMS object loading is completed, then initiate OBTF compilation Run TFDBCompileRun.bat in windows (TFDBCompileRun.sh in linux)

Check for the Invalid Count and make sure that the Invalid count is '0'. Please run Invalid Recompilation script(fast.sql), if required. Please provide number of threads and schema name as input while running the script.

This is for KERNEL as well as cluster objects in DB schema.

Please run Gateway Standard XML (Gwtm_Standard_Xml.sql) script. The data in the script is necessary to execute gateway summary operations.



1.3.2 Basic Setup using GUI Installer

The steps to load objects from the shipment media are given below:

 Double-click 'FCUBSInstaller.bat' batch file to launch Oracle Banking Trade Finance Universal Installer. The following screen is displayed. Select Utilities option and click 'Next' button.



S Oracle FLEXCUBE Universal Installer	out fractions	
Oracle Banking Installer		ORACLE INSTALLER
Welcome To Oracle Universal Banking Installer		
Prerequisites		
 Oracle Database should be Installed. JDK should be Installed. 		
Please specify the JDK and Oracle Home path.		
JDK Path	Browse	
Oracle Home Path	Browse	
Please select any one of the below options:		
Property File creation		
Utilities		
Exit Log	Bac	Next

2. Select 'Day Zero Setup' in Utility Screen and click Next as shown below:



Soracle FLEXCUBE Universal Installer	X 🗆 🗖
Oracle Banking Installer	
Select an Utility:	
Day Zero Setup	
O User Creation	
O DSN Entries	
O Entity Details	
SMS DSN Entries	
Switch Monitor Installation	
ENV Property file operations	
Exit	Back Next

3. Click 'Next' and in the below screen. OBTF Schema details to be entered is displayed:



Provide SMS schema details.		
Name	Value	
Jsername	installer	
Password	•••••	
Service Name	testdb	
P Address	10.10.10	
Port	1521	
FNS Connect Descriptor	testdb	Test Connection
Name	Value	
Jsername	installer	Same as SMS Schema
Password	••••••	
Service Name	testdb	
P Address	10.10.10	
Port	1521	
FNS Connect Descriptor	testdb	Test Connection
		Test Connection

Specify the following schema details:

User Name

Specify the user name to access the schema.

Password

Enter the schema password.

Service Name

Provide service name of database.

IP Address

Specify the IP address of the system where the database schema is installed.

Note: IP Address should be same as mentioned in the TNSnames.ora

Port

Specify the port number.

TNS Connect Descriptor

Specify the TNS Connect Descriptor.

Here Entity Schema is mandatory, atleast minimum one entry should be provided.



Entity Id value is default i.e. 'ENTITY_ID1' for first entry.

Provide the JNDI Name for the ENTITY_ID1. By default the jndi name is 'jdbc/fcjdevDS' Give the Schema Details for the Entity1.

Here Compile In All Entities Field is 'N'. (As using the Single Entity Concept).

4. Click 'Next' and the following screen is displayed:

Oracle FLEXCUBE Universal Installer Image: Control of the second secon					
	s of CSTB_PARAM table in the Datab				
S.No.	Param Name	Param value			
1	PW_OUR_STD_CCY_DEFAULT	Y	-		
2	SSN_MASK_FORMAT	ann-an-naaa			
3	TRACK_LIABILITY	Y			
4	PROJFINCMTRATE	INTEREST_RATE			
5	ELCM_USER_ID	SYSTEM			
6	STMT_SPOOL_PATH	/home/fcubs/logs			
7	CHUNK_SIZE	Y			
8	PROJFINCMTMARGIN	MARGIN			
9	WORKFLOW_SESSION_TIMEOUT	50			
10	OR_ADMINROLE	OR-SUPERVISOR			
11	NOTIF_LOG	Y			
12	FCIS_INSTALLED	N			
13	PROPOGATION_OF_LOH	N			
14	SMTP_USERID				
15	COMMITMENT_UDE_NAME	INTEREST_RATE			
16	DEFER_LOCAL_LIMITS	Y			
17	PC_OUTFILE_PATH	/home/fcubs/gilog/gi/outgoing/data			
18	ELCM_CCY_REV_LIAB_BR	Y			
19	SPREAD_APPLICATION	В	-		
Exit Log Back Next					

5. Screen displays basic setup details for table 'CSTB_PARAM'.

Here Oracle directory name(present in all_directories table in the schema) must be added for WORK_AREA and TRACE_AREA. Oracle directory name must be added for other required parameters also.

Oracle directory creation in the schema can be done as below :

Create or replace directory dir_name as 'directory_path';

6. Click on 'Next' button to display Limits integration Parameters Screen as shown below:



S Oracle FLEXCUBE Universal Installer		
Oracle Banking Installer		
LIMITS INTEGRATION PARAMETERS Parameters of CSTB_PARAM table in the Database.		
FCUBS PROPERTY FILE		Browse
LIMITS SETUP MODE	STANDALONE -	
LIMITS COMMUNICATION MODE	ASYNCHRONOUS	
OBCL LIMITS COMMUNICATION MODE	ASYNCHRONOUS -	
Exit Log	Back	Vext

Limits Integration Parameters will be set based on values read from fcubs.properties file browsed.

7. Click on 'Next' button .Screen displays parameters for table SMTB_MODULES_GROUP

If any change is required in the JNDI name, edit the same and click on Update.



🖆 Oracle FLEXCUBE Universal Installer 12.5.0.0.0 🗖 🖻 🔀					
Orac	le Banking Installer			DRACLE NSTALLER	
Basic Setu Parameter	IP Details s of SMTB_MODULES_GROUP table	in the Database. Update			
MODULE	MODULE DESCRIPTION	JNDINAME			
FCSMS	SMS	jdbc/fcjdevDS			
FCCOMN	Core Services	jdbc/fcjdevDS			
FCELCM	ELCM	jdbc/fcjdevDS_EL			
FCCPLN	Oracle FLEXCUBE Corporate Len	jdbc/fcjdevDS			
•	III				
Exi	t Log		Back	Next	

8. Click 'Next'. The following screen is displayed.



🛃 Oracle FLEXCUBE Universal Installer 12.5.0.0.0					
Oracle Banking I	nstaller				
Basic Setup Details Basic Details for bank and br	anch				
Bank Code	CH0	Cheque Number Mask	NNNN		
Bank Name	City Head Office	Host Code	HOST1		
Branch Code	000	Process Deployment	BPEL 💌		
Country Code		TimeZone	Asia/Calcutta		
Country Description					
	e Date Format must be yyyy/mm/	/dd.			
Input Date	2018/04/20				
Current Business Date	2018/04/20				
Previous Business Date	2018/04/19				
Next Business Date	2018/04/21				
Next To Next Business Date	2018/04/22				
Exit Log		(Back Next		

Screen displays basic setup details for bank and branch

Bank Code

Enter the bank code.

Bank Name

Enter the bank name.

Branch Code

Enter the branch code.

Country Code

Enter the Country code.

Country Description

Enter the Country Description.

Cheque Number Mask

Enter the Cheque Number Mask

Process Deployment

Choose mode of process deployment between BPEL or BPMN



Screen also displays basic setup details for dates.

Input Date

Enter the input date.

Current Business Date

Enter the current business date.

Previous Business Date

Enter the previous business date.

Next Business Date

Enter the next business date.

Next to Next Business Date

Enter the next to next business date.

9. Click 'Next'. The following screen is displayed.

🤹 Oracle F	LEXCUBE Universal Installer 12.5.	0.0.0		
Ora	cle Banking Install	er		
Basic S	etup Details			
Curren	cy Details.			
Local C	urrency Code	L	JSD	
Local C	urrency Name	L	JS DOLLAR	
Current	Fin Cycle	2	2011 🔽	
Current	Fin Period	C	QT1 💌	
ISO Cu	rrency Code	2	294	
Exte	ernal Password			
No	User Name	Password or LDAP User n	ame	
1	ADMINUSER1	•••••		
2	ADMINUSER2	•••••		
· · · · · · · · · · · · · · · · · · ·				
E	tit Log			Back Next

Screen displays basic setup details for currency, User can change them.

Local Currency Code

Enter Local Currency Code



Local Currency Name

Enter Local Currency Name

Current Fin Cycle

Enter Current Financial Cycle(any year from 2011 to 2050)

Current Fin Period

Enter Current Financial Period(QT1 to QT4,M01 to M12)

ISO Currency Code

Enter ISO Currency Code.

Screen also displays basic setup details for the creating a user in Banking Trade Finance.

Creation of 'SYSTEM' user is mandatory for payments processing, it needs to be created as part of static data setup.

External Password

Check this box to specify the external password.

User Name

Displays the user name. Change the user name if required.

Password or LDAP User Name

Specify the password and it is mandatory. You can use the following characters in the password:

- Alphabets in uppercase
- Alphabets in lowercase
- Numerals

[™]You cannot use '_' (underscore) in the password.

10. Click 'Next' and the following screen is displayed:




S Oracle FLEXCUBE Universal Installer	
Oracle Banking Installer	
Basic Setup Details	
Current screen Displays the status of the Basic Setup.	
0%	
Start Setup SMS users Log	
Exit Log	Back Next

Click 'Start Setup' button to compile the entries. On completion the below Screen will be seen.
 User created logs can be viewed by clicking SMS uses Log button.



S Oracle FLEXCUBE Universal Installer		
Oracle Banking Installer		
Basic Setup Details Current screen Displays the status of the Basic Setup.		
100%		
	•	
Start Setup SMS users Log		
Exit		Back Next
Message		



This completes the basic setup process.





Installer Database Setup [November] [2022] Version 14.7.0.0.0

Oracle Financial Services Software Limited Oracle Park Off Western Express Highway Goregaon (East) Mumbai, Maharashtra 400 063 India Worldwide Inquiries: Phone: +91 22 6718 3000 Fax: +91 22 6718 3001 https://www.oracle.com/industries/financial-services/index.html

Copyright © [2020, 2022], Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.