Standalone Scheduler Property File Creation Oracle Banking Payments Release 14.7.4.0.0 [June] [2024]



# **Table of Contents**

| 1. Cre | ating Property File for Standalone Scheduler |      |
|--------|--|------|
| 1.1    | Introduction                                 |      |
| 1.2    | Creating Property File                       |      |
| 1.2.1  |  |      |
| 1.2.2  | Setting Common Properties                    | 1-7  |
| 1.2.3  | Single Sign on                               |      |
| 1.2.4  |  |      |
| 1.2.5  | Configuring Scheduler Queues                 | 1-11 |
| 1.2.6  | Setting EMS FTP/FTPS Properties              | 1-16 |
| 1.2.7  | Saving Property File                         | 1-22 |

## ORACLE

# 1. Creating Property File for Standalone Scheduler

## 1.1 Introduction

This chapter explains the steps to create property file for Standalone Scheduler.

## 1.2 Creating Property File

To create the property file for Oracle Banking Payments, follow the steps given below:

1. Launch Oracle Banking Universal Installer. Select 'Property File Creation' option and Click 'Next' button.



| 🕌 Oracle FLEXCUBE Univers                                 | al Installer 12.5.0.0.0               |        | - 🗆 X   |
|---|---------------------------------------|--------|---------|
| Oracle Bankir   | ng Installer                          |        | STALLER |
| Welcome To Oracle Unive                                   | ersal Banking Installer               |        |         |
| Prerequisites   |                                       |        |         |
| <ul> <li>Oracle Databas</li> <li>JDK should be</li> </ul> | e should be installed.<br>Installed.  |        |         |
| Please specify the JDK an                                 | d Oracle Home path.                   |        |         |
| JDK Path  | C:/Program Files/Java/jdk1.8.0_311    | Browse |         |
| Oracle Home Path  | D:/app/client/product/19.0.0/client_1 | Browse |         |
| Configuration Mode  | Normal                                |        |         |
| Please select any one of t                                | he below options:                     |        |         |
| Property File creation                                    |                                       |        |         |
|   |                                       |        |         |
|   |                                       |        |         |
|   |                                       |        |         |
| Exit Log  |                                       | Back   | Next    |

2. Select 'Scheduler' component and appropriate plugin if needed



| Oracle Banking Instal               | er  |        |  |  |  |
|-------------------------------------|---|--------|--|--|--|
| Select one of the Components        |   |        |  |  |  |
| Load Existing Property File         |   | Browse |  |  |  |
| ◯ INFRA                             | eway O Switch Interface Installation        |        |  |  |  |
| Select Oracle Product Processors    |   |        |  |  |  |
| 🔲 Oracle FLEXCUBE Universal Banking | í l   |        |  |  |  |
| Oracle FLEXCUBE Enterprise Limits   | and Collateral Management (CO-DEPLOY)       |        |  |  |  |
| ✓ Oracle Banking Payments           |   |        |  |  |  |
| Oracle Banking Corporate Lending    | Open Development Tool                       |        |  |  |  |
| Oracle Banking Treasury             | Oracle FLEXCUBE Universal Banking for JAPAN |        |  |  |  |
| Oracle Banking Trade Finance        | Oracle Banking Trade Finance                |        |  |  |  |
| Select Plugins to be Installed      |   |        |  |  |  |
| Host Address 10.10.10.10 1010       | Origination Scheduler Standalone            |        |  |  |  |
| <b>Reports</b> 10.10.10.10 1010     | SIANET Adapter                              |        |  |  |  |
| DMS 10.10.10.10 1010                | Insulation External Adapter required        |        |  |  |  |
|                                     |   |        |  |  |  |
|                                     |   |        |  |  |  |
| Exit Log                            | Back  | Next   |  |  |  |

ORACLE

3. The below Screen accepts EAR name, Context Name, Application Server Path, Source Path and EAR Destination path. Enter the valid data and select File Seperator Style and application server from drop down.

| 🛃 Oracle FLEXCUBE Universal Installer 14.2.0.0.0 |            |  |           |  |
|--|------------|--|-----------|--|
| Oracle Bar                                       | nking Inst | aller  |           |  |
| Provide Environmen                               | t details. |  |           |  |
| EAR Name   | FCUBS      |  |           |  |
| Context Name                                     | FCJNeoWeb  |  |           |  |
| File Seperator Style                             | Linux      | V  |           |  |
| Application Server                               | Weblogic   | <b>•</b>   |           |  |
|  |            |  |           |  |
| Application Server Pa                            | ath        | D:/oracle/wls12210/wlserver                          | Browse    |  |
| Source Path                                      |            | D:/14.10sdc/14.2.0.0.0/OB_PAYMENTS_14.2.0.0.0_GA_OUT | Browse    |  |
| Ear Destination Path                             |            | D:/14.10sdc/14.2.0.0.0/OB_PAYMENTS_14.2.0.0.0_GA_OUT | Browse    |  |
|  |            |  |           |  |
|  |            |  |           |  |
|  |            |  |           |  |
|  |            |  |           |  |
|  |            |  |           |  |
|  |            |  |           |  |
| Exit   | Log        |  | Back Next |  |

- 4. Click on 'Next' button to navigate to below Screen.
- 5. Below shown Screen contains:

#### Release

Select the release from the adjoining drop down list.

Hashing Algorithm Iteration Count and Security key for encryption logic should be entered which will be used for encryption. By default the value is 'oraclefinancials'.



| Soracle FLEXCUBE Universal Installer 14.2.0.0.0 |                  | X         |
|---|------------------|-----------|
| Oracle Banking Installer                        |                  |           |
| Property File Creation                          |                  |           |
|   |                  |           |
|   |                  |           |
|   |                  |           |
| Release   | KERNEL           |           |
| Hashing Algorithm Iteration Count               | 10000            |           |
| Security Key for Encryption Logic               | oraclefinancials |           |
|   |                  |           |
|   |                  |           |
|   |                  |           |
|   |                  |           |
|   |                  |           |
|   |                  |           |
|   |                  |           |
| Exit Log  |                  | Back Next |



### 1.2.1 Configuring Scheduler

This section describes the method to configure scheduler data source.

|   | staller 14.2.0.0.0                 |  |  |  |
|---|------------------------------------|--|--|--|
| Oracle Banking  | Installer                          |  |  |  |
| Property File Creation - DataSource                                     |                                    |  |  |  |
| Please enter DataSource N   | lames                              |  |  |  |
| SMS Data Source   | jdbc/fcjsmsDS                      |  |  |  |
| Branch Data Source  | jdbc/fcjdevDSBranch                |  |  |  |
| Scheduler Data Source   | jdbc/fcjSchedulerDS                |  |  |  |
| PM Online JNDI  | jdbc/fcjpmDS                       |  |  |  |
| PM Batch JNDI   | jdbc/fcjpmDS                       |  |  |  |
|   |                                    |  |  |  |
| Webservices Provider URL  | t3://localhost:7001/               |  |  |  |
|   |                                    |  |  |  |
| Webservices Provider URL<br>Host Server URL<br>Standalone Scheduler URI | https://10.10.10.10:1010/FCJNeoWeb |  |  |  |
| Host Server URL   | https://10.10.10.10:1010/FCJNeoWeb |  |  |  |
| Host Server URL   | https://10.10.10.10:1010/FCJNeoWeb |  |  |  |
| Host Server URL   | https://10.10.10.10:1010/FCJNeoWeb |  |  |  |
| Host Server URL   | https://10.10.10.10:1010/FCJNeoWeb |  |  |  |

2. Specify the following details:

#### Scheduler Datasource

Specify the scheduler datasource which Oracle Banking Payments will access.



### 1.2.2 <u>Setting Common Properties</u>

This section describes the process of setting common properties of Standalone Installer.

1. The installer displays the 'Common Properties' screen.

| 🛓 Oracle FLEXCUBE Universal Installer 14.2.0.0.0            |  |                                   |   |  |
|---|--|-----------------------------------|---|--|
| Oracle Banki  | ng Installer                                       |                                   |   |  |
| Property File Creation<br>Debug Logs Required<br>Work Area  | - General Property Yes LOV Fetch Required /BmDbgs/ | Auto clear User                   | YES   |  |
| Signature Path<br>Excel Path                                | /BrnDbgs/<br>/BrnDbgs/                             | Auto clear oser                   |   |  |
| Request Time Out<br>Connection Time Out<br>Session Time Out | 1800000milli seconds3600Seconds1800Seconds         | Max Image Size<br>User Batch Time | 1048576         Bytes           0         Hours |  |
| CSS Style   | Default  | Name                              | Flexblue  |  |
| Language  | ENGLISH  | ISO Code                          | en  |  |
| Application Title   | FLEXCUBE UBS                                       |                                   |   |  |
| Version   | 14.2.0.0.0   |                                   |   |  |
| CopyRights  | Copyright © 2017,2018, Oracle and/or its affili:   | ates. All rights reserved.        |   |  |
| Exit Log Back Next  |  |                                   |   |  |

2. Specify the following details:

#### **Debug Logs Required**

If you require debug option, select 'Yes' from the drop-down list. If you do not require debug option, select 'No'.

#### Work Area



Specify the work area.

For example: D:\BrnDbgs\

#### **Signature Path**

Specify the location at which the signature images are placed.

#### **Excel Path**

Specify the location at which the excel files are generated.

#### Request Time Out

Specify the database request timeout value in milli seconds. This is the maximum number of seconds the database waits for a query to return the result.

#### **Connection Time Out**

Specify the database connection timeout value in seconds. This is the maximum number of seconds the application waits for a connection to the database to open.

#### Session Time Out

Enter the session time out value in seconds. This is the maximum number of seconds during which the application gets active without any user intervention. If there is no user intervention continuously for the duration specified here, the user session gets expire.

#### LOV Fetch Required

If you check this box, the option lists in Oracle Banking Payments displays the matching values based on the first characters that you enter in a field. If you specify the first three characters of a value to be entered in an option list and tab out, the system displays the complete list of values that are matching the first three characters.

If you do not check this, option lists does not show the matching values based on the first few characters. You need to specify the complete value against the field.

Click 'Next' and the following screen is displayed:

#### CSS style

Select Default or Custom from dropdown. By Default CSS Style name will be 'flexblue'.

#### Language

Select language from the dropdown.

Version and Copyright are other general properties.

Click on Next button, once all the property details are entered.

#### 1.2.3 Single Sign on



| Only 'Platform Security' option will be enabled for Scheduler. Select the op | otion if needed. |
|--|------------------|
|--|------------------|

| Oracle | Banking Installer                                      |  |  |  |
|--------|--|--|--|--|
| Prop   | erty File Creation - Single Sign on                    |  |  |  |
| SSO    | Required   | SSO Type   |  |  |
| SSO    | KEY DN   |  |  |  |
| Auth   | Authentication details maintained external to FLEXCUBE |  |  |  |
| Exter  | nal Password Required                                  | Authentication Type MSAD                                   |  |  |
| Exter  | nal User Login Required 📃                              |  |  |  |
|        | Pla  | form Security SMS Security Key oraclefinancials            |  |  |
| Optic  | on to provide LDAP server details                      |  |  |  |
| No.    | Name   | Value  |  |  |
| 1      | LDAP SERVER URL  | LDAP://10.10.10.10.111                                     |  |  |
| 2      | LDAP SSL ENABLED                                       |  |  |  |
| 3      | SECURITY AUTHENTICATION TYPE                           | Simple   |  |  |
| 4      | DOMAIN NAME  | flexcube.com   |  |  |
| 5      | LDAP SERVER TIMEOUT                                    | 0  |  |  |
| Optio  | on to provide SAML details                             |  |  |  |
| No.    | Name   | Value  |  |  |
| 1      | SAML CERTIFICATE PATH                                  | D:\Security\SAML_Implementation\TestFiles\cert\certstore\b |  |  |
| 2      | SAML CERTIFICATE PASSWORD                              | •••••  |  |  |
| 3      | SAML CERTIFICATE ALIAS                                 | barc   |  |  |
| 4      | SAML VALID AUDIENCE                                    | bPAID_BWSIT  |  |  |
|        |  |  |  |  |
| Exit   | Log  | Back Next  |  |  |

## 1.2.4 SMTPS Details

SMPTS mail configuration is enabled for Scheduler.

Specify the below details:

Host: Specify the SMTP host name.

User ID: Specify the user ID.

User Password: Specify the user password.

ORACLE

JNDI Name: Specify the JNDI name.

| Oracle FLEXCUBE Universal Installer |   |   |          |  |
|-------------------------------------|---|---|----------|--|
| 0                                   | racle Banking Installe                            | r <u> </u>  | NSTALLER |  |
| Prope                               | Property File Creation - SMTPS/Branch/DMS         |   |          |  |
| Option                              | Option for Mail configuring using SMTPS Protocol. |   |          |  |
| No.                                 | Name  | Value   |          |  |
| 1                                   | Host  | samplename.mail.com                                       |          |  |
| 2                                   | UserId  | infra   |          |  |
| 3                                   | User Password                                     | *****   |          |  |
| 4                                   | JNDI Name   | mail/FCUBSMail  |          |  |
| Option                              | n for modifying the Branch properties.            |   |          |  |
| No.                                 | Name  | Value   |          |  |
| 1                                   | Date Seperator                                    | -   | ▲        |  |
| 2                                   | WorkFLow Frequency                                | 6000  |          |  |
| 3                                   | Compress Request                                  | V   | •        |  |
| Option                              | n for modifying the DMS/IPM property v            | alues.  |          |  |
| No.                                 | Name  | Value   |          |  |
| 1                                   | Login Service Address                             | http://10.10.10.10:1010/imaging/ws/LoginService           | ▲        |  |
| 2                                   | Document Service Address                          | http://10.10.10.1010/imaging/ws/DocumentService           | _        |  |
| 3                                   | Document Content Service Address                  | http://10.10.10.10:1010/imaging/ws/DocumentContentService |          |  |
| 4                                   | IPM User Name                                     | testuser  |          |  |
| 5                                   | IPM Password                                      | •••••   | •        |  |
|                                     |   |   |          |  |
|                                     | Exit Log Back Next                                |   |          |  |

ORACLE

## 1.2.5 Configuring Scheduler Queues

This section describes the method to configure scheduler Queues.

1. System displays the following screen:

| 🖆 Oracle FLEXCUBE Universal Installer 14.2.0.0.0   |   |  |  |
|--|---|--|--|
| Oracle Banking Installer   |   |  |  |
| Property File Creation - Scheduler Queues Option for configuring Scheduler Destination Queue Notify Destination  | Option for configuring Scheduler Deferred Queue Notify Deffered Queue Name DEFFERED_DEST_QUEUE  |  |  |
| Queue Name     NOTIFY_DEST_QUEUE       Queue Connection Factory     NotifyDestQCF       Secure     Caller ID       Caller Password     Notify Queue Location | Deffered Queue Connection Factory DefferedDestQCF   |  |  |
| Notify Queue Name     NOTIFY_QUEUE       Dead Letter Queue Name     NOTIFY_QUEUE_DLQ   | Option for configuring Log Rotation Interval Scheduler Log Rotation Interval WEEKLY Option for Enternal Degree configuration for Destination Output |  |  |
| Notify Queue Connection Factory NOTIFY_MDB_QCF   | No.     Name     Value       1     Provider URL     liop://localhost:1010       2     Security Principal     ••••••••••••••••••••••••••••••••••••   |  |  |
| Exit Log   | Back Next   |  |  |

1. Specify the following details:

#### **Notify Destination**

Specify the notify destination. Select one of the following options:

- QUEUE
- TOPIC

#### Queue Name

Set 'NOTIFY\_DEST\_QUEUE' as the destination queue name.

#### **Queue Connection Factory**

Set 'NotifyDestTCF' as the queue connection factory.

#### Secure

Check this box to indicate that it is a secured queue connection factory. If you check this box, you will be prompted to specify the caller ID and caller password as shown in the following screen.

| 🔮 Oracle FLEXCUBE Universal Installer 14.2.0.0.0       |   |  |  |
|--|---|--|--|
| Oracle Banking Installer                               |   |  |  |
| Property File Creation - Scheduler Queues              |   |  |  |
| Option for configuring Scheduler Destination Queue     | Option for configuring Scheduler Deferred Queue                 |  |  |
| Notify Destination                                     | Notify Deffered Queue Name DEFFERED_DEST_QUEUE                  |  |  |
| Queue Name NOTIFY_DEST_QUEUE                           | Deffered Queue Connection Factory DefferedDestQCF               |  |  |
| Queue Connection Factory NotifyDestQCF                 | Secure Caller ID  |  |  |
| Secure Caller ID                                       | Caller Password   |  |  |
| Caller Password  |   |  |  |
| Notify Queue Location                                  |   |  |  |
| Option for configuring Scheduler Notify Internal Queue | Option for configuring Log Rotation Interval                    |  |  |
| Notify Queue Name NOTIFY_QUEUE                         | Scheduler Log Rotation Interval WEEKLY                          |  |  |
| Dead Letter Queue Name NOTIFY_QUEUE_DLQ                | Option for External Server configuration for Destination Queue. |  |  |
| Notify Queue Connection Factory NOTIFY_MDB_QCF         | No. Name Value  |  |  |
| Secure Caller ID                                       | 1 Provider URL iiop://localhost:1010                            |  |  |
| Caller Password  | 2 Security Principal  |  |  |
|  | 3 Security Credential   |  |  |
|  |   |  |  |
| Exit Log   | Back  |  |  |

#### **Caller ID**

Specify the caller ID for the secured queue connection factory.

#### **Caller Password**

Specify the password for the caller ID to access the secured queue connection factory.

If the queue connection factory is not secured, i.e., if you have not checked the box 'Secure', the installer will not display the fields 'Caller ID' and 'Caller Password'. You need not provide these details in that case.

#### Notify Queue Location



Specify the notify queue location. Select one of the following options:

- Internal
- External

For Oracle WebLogic application server, the notify queue location should be selected as 'Internal'. If you choose 'Internal' as the 'Notify Queue Location', the screen provided in the following step does not get displayed. You will be navigated to next step where you can specify the notify deferred queue name and connection factory.

2. If you choose 'External', system displays the following screen:

| S Oracle FLEXCUBE Universal Installer 14.2.0.0.0  |   |
|---|---|
| Oracle Banking Installer  |   |
| Property File Creation - Scheduler Queues   |   |
| Option for configuring Scheduler Destination Queue  | Option for configuring Scheduler Deferred Queue   |
| Notify Destination     QUEUE       Queue Name     NOTIFY_DEST_QUEUE       Queue Connection Factory     NotifyDestQCF       Secure     Caller ID       Caller Password     Image: Content of the secure of | Notify Deffered Queue NameDEFFERED_DEST_QUEUEDeffered Queue Connection FactoryDefferedDestQCFSecureCaller ID  |
| Notify Queue Location   | Option for configuring Log Rotation Interval  |
| Notify Queue Name     NOTIFY_QUEUE       Dead Letter Queue Name     NOTIFY_QUEUE_DLQ       Notify Queue Connection Factory     NOTIFY_MDB_QCF   | Scheduler Log Rotation Interval WEEKLY Option for External Server configuration for Destination Queue.  |
| Caller Password   | No.         Name         Value           1         Provider URL         iiop://localhost:1010           2         Security Principal         •••••••••••••••••••••••••••••••••••• |
| Exit Log  | Back Next   |

3. Specify the following details of the external queue. **Provider URL** 

Specify the provide URL (iiop://localhost:1010).



1010 is the default IIOP port.

| Application Server | EMS Out Initial Context Factory   |
|--------------------|---|
| Oracle WebLogic    | t3:// <ip_adress>:port<br/>For example: t3://10.10.10.10:1010</ip_adress>   |
|                    | Here, 10.10.10.10 represents the local host and 1010<br>to the target server default port<br>(AdminServer/ManagedServer). |

#### **Security Principal**

Specify the login ID to access the application server.

#### **Security Credentials**

Specify the password to access the application server.

4. Click 'Next' to proceed with scheduler configuration.

If you choose 'Internal' as the 'Notify Queue Location', you will be directly navigated to the following screen. In that case, the installer will not show the screen explained in the previous step.



| S Oracle FLEXCUBE Universal Installer 14.2.0.0.0  |   | x  |
|---|---|----|
| Oracle Banking Installer  |   |    |
| Property File Creation - Scheduler Queues   |   |    |
| Option for configuring Scheduler Destination Queue  | Option for configuring Scheduler Deferred Queue   |    |
| Notify Destination     QUEUE       Queue Name     NOTIFY_DEST_QUEUE       Queue Connection Factory     NotifyDestQCF       Secure     Caller ID       Caller Password     Image: Caller ID       Notify Queue Location     Image: Caller ID | Notify Deffered Queue Name       DEFFERED_DEST_QUEUE         Deffered Queue Connection Factory       DefferedDestQCF         Secure       Caller ID         Caller Password |    |
| Option for configuring Scheduler Notify Internal Queue  | Option for configuring Log Rotation Interval  |    |
| Notify Queue Name     NOTIFY_QUEUE       Dead Letter Queue Name     NOTIFY_QUEUE_DLQ       Notify Queue Connection Factory     NOTIFY_MDB_QCF   | Scheduler Log Rotation Interval     WEEKLY       Option for External Server configuration for Destination Queue       No.     Name       Value                              | ə. |
| Caller Password   | Provider URL iiop://localhost:1010     Security Principal •••••••••••   |    |
|   | 3 Security Credential   | ]  |
| Exit Log  | Back Next   |    |

5. Specify the following details:

#### **Notify Deffered Queue Name**

Set 'DEFFERED\_DEST\_QUEUE' as the notify differed queue name.

#### **Deffered Queue Connection Factory**

Set 'DefferedDestQcf' as the deffered queue connection factory.

#### Secure

Check this box to indicate that it is a secured deferred queue connection factory. If you check this box, you will be prompted to enter the caller ID and caller password as shown in the following screen.

- 6. Specify the caller ID and caller password for the secured deferred queue connection factory.
- 7. Click 'Next' and the following screen is displayed:
- 8. Specify the following details:



#### **Notify Queue Name**

Set 'NOTIFY\_QUEUE' as the notify queue name.

#### Dead Letter Queue Name

Set 'NOTIFY\_QUEUE DLQ' as the dead letter queue name.

#### Notify Queue Connection Factory

Set 'NOTIFY\_MDB\_QCF' as the notify queue connection factory.

#### Secure

Check this box to indicate that it is a secured queue connection factory. If you check this box, you will be prompted to enter the caller ID and caller password as shown in the following screen.

- 9. Specify the caller ID and caller password for the secured notify queue connection factory.
- 10. Click 'Next' and the following screen is displayed:

#### 1.2.6 Setting EMS FTP/FTPS Properties

You will be navigated to the 'Scheduler EMS Properties' screen. Here, you need to set the EMS details.

1. Set the EMS properties:



| Oracle Banking Installer                     |                                   |                    |  |  |
|--|-----------------------------------|--------------------|--|--|
| Property File Creation - Scheduler EMS Queue |                                   |                    |  |  |
| No.  | Name                              | Value              |  |  |
|  | Incoming Dead Letter Queue Name   | EMS_QUEUE_DLQ      |  |  |
| 2  | Incoming backup Queue Name        | EMS_QUEUE_BACK     |  |  |
| }  | Incoming Queue Connection Factory | EmsQcf             |  |  |
| Ļ  | Secure Incoming Queue Connection  |                    |  |  |
| ;  | Incoming Queue Caller Id          |                    |  |  |
| ;  | Incoming Queue Caller Password    |                    |  |  |
| ,  | Outgoing Dead Letter Queue Name   | EMS_QUEUE_DLQ      |  |  |
|  | Outgoing Queue Connection Factory | EmsQcf             |  |  |
| )  | Secure Outgoing Queue Connection  |                    |  |  |
| 0  | Outgoing Queue Caller Id          |                    |  |  |
| 1  | Outgoing Queue Caller Password    |                    |  |  |
| 2  | Outgoing Queue Provider URL       | t3://10.10.10:1010 |  |  |
| 3  | Queue Principal                   | ••••               |  |  |
| 4  | Queue Credential                  | ••••               |  |  |
| 5  | Incoming Queue Name               | EMS_INQUEUE        |  |  |
| 6  | Outgoing Queue Name               | EMS_OUTQUEUE       |  |  |
| 7  | SFMS Incoming Queue               | SFMS_INQUEUE       |  |  |
| 8  | RTGS Incoming Queue               | RTGS_INQUEUE       |  |  |
| 9  | EMS Bulker Queue                  | BULKER_QUEUE       |  |  |
|  |                                   |                    |  |  |

2. Specify the following details:

#### **OutGoing Connection Factory**

Specify the name of the outgoing connection factory to which EMS listens. You need to create this connection factory at the application server.

For details on connection factory creation, follow the steps described for creation of notify connection factories.

#### **Incoming Connection Factory**

Specify the name of the incoming connection factory to which EMS listens. You need to create this connection factory at the application server.



For details on connection factory creation, follow the steps described for creation of notify connection factories.

#### **Outgoing Queue Name**

Specify the name of the outgoing queue for which EMS is configured. By default, this is set as 'NOTIFY\_QUEUE\_DLQ'.

#### Incoming Queue Name

Specify the name of the incoming queue for which EMS is configured. By default, this is set as 'NOTIFY\_QUEUE\_DLQ'.

#### Incoming Backup Queue Name

Specify the name of the incoming backup queue for which EMS is configured.

#### **Outgoing Queue Provider URL**

In case EMS OUT MDB is to be configured to queue, you need to specify the URL for outgoing provider based on the application server. By default, the Installer displays the outgoing queue provider URL for Oracle WebLogic.

This value is application server dependent.

The details of Outgoing Queue Provider URL to be used for different application servers are given below:

| Application Server | EMS Out Initial Context Factory   |
|--------------------|---|
| Oracle WebLogic    | t3:// <ip_adress>:port</ip_adress>  |
|                    | E.g.: t3://10.10.10.10:1010   |
|                    | Here, 10.10.10.10 represents the local host and 1010 to the target server default port (AdminServer/ManagedServer). |

#### Queue Principal

If EMS OUT MDB has to be configured to queue, you need to specify the EMS out queue principal. This is the user name for the application server in which the queue is configured.

#### Queue Credential

If EMS OUT MDB has to be configured to queue, you need to specify the EMS out queue credential. This is the password for the above user name created for application server in which the queue configured.

#### Incoming Queue Name

Specify the incoming queue name.

#### **Outgoing Queue Name**

Specify the outgoing queue name.

#### SFMS Incoming Queue

Specify the SFMS Incoming Queue.

#### **RTGS Incoming Queue**

Specify the RTGS incoming Queue.

#### EMS Bulker Queue

Specify the EMS Bulker Queue.

#### 3. Once you have specified the above details, click 'Next' and the following screen is displayed:

| Oracle        | FLEXCUBE Universal Installer 14.2 | .0.0.0           | and the second se |           |
|---------------|-----------------------------------|------------------|---|-----------|
| Ora           | cle Banking Instal                | er               |   |           |
| 1.00          | rty file Creation - EMS FTP/FTPS  |                  |   |           |
| No.           | Name                              | Value            |   |           |
| 1             | File TranferMode FTPS             | FTPS             |   |           |
| 2             | Server                            | 10.10.10         |   |           |
| 3             | User id                           | OFSS             |   |           |
| 4             | Password                          | •••••            |   |           |
| 5             | KnownHost file local folder path  | /mnt/ems/SFTP/   |   |           |
| 6             | KnownHost file server folder part | h /mnt/ems/SFTP/ | =   |           |
| 7             | File Type                         | .txt             |   |           |
| 8             | SWIFT Format                      | 1                |   |           |
| 9             | SWIFT Message Delimiter           |                  |   |           |
| 10            | SWIFT Message Terminator          |                  |   |           |
| 11            | MEDIA                             | SWIFT            | -   |           |
| Option<br>No. | n for EMS -Structured Financial M | Value            |   |           |
| 1             | Signature Block                   |                  | <b>^</b>  |           |
| 2             | Keystore File Name /keystore      |                  | =   |           |
| 3             | Keystore Alias name               | ••••             | <b>_</b>  |           |
| 4             | Kovetoro Paceword                 |                  |   |           |
| E             | Exit                              |                  |   | Back Next |
|               |                                   | 1-19             |   | ORACL     |

4. Specify the following details:

#### File Transfer Mode FTPS

Specify the mode of transferring files to EMS. Select one of the following:

- FTPS
- SFTP
- HTTP

#### Server

Specify the server IP address for the selected file transfer mode.

#### User ID

Specify the user ID to access the server of the file transfer mode.

#### Password

Specify the password to for the above user ID.

#### File Type

Specify the type of file that is transferred. By default, the Installer sets it as '.txt'.

#### SWIFT Message Delimiter

Specify the character which is used as the message delimiter.

#### SWIFT Message Terminator

Specify the character which is used as the message terminator.

5. Once you have specified the above details, click 'Next'. and the following screen is displayed:



| Oracle Banking Installer Oracle Banking Installer |  |  |          |           |
|---|--|--|----------|-----------|
|   | erty file Creation - EMS FTP/FTPS<br>n for Scheduler EMS FTP/FTPS co |  |          |           |
| No.   | Name   | Value                                  |          |           |
| 1   | File TranferMode FTPS  | FTPS                                   | <b>_</b> |           |
| 2   | Server   | 10.10.10                               |          |           |
| 3   | Userid   | OFSS                                   |          |           |
| 4   | Password   |  |          |           |
| 5   | KnownHost file local folder path                                     | /mnt/ems/SFTP/                         |          |           |
| 6   | KnownHost file server folder pat                                     | h /mnt/ems/SFTP/                       | =        |           |
| 7   | File Type  | .txt                                   |          |           |
| 8   | SWIFT Format   | 1                                      |          |           |
| 9   | SWIFT Message Delimiter  |  |          |           |
| 10  | SWIFT Message Terminator   |  |          |           |
| 11  | MEDIA  | SWIFT                                  |          |           |
| Option  | n for EMS -Structured Financial Me                                   | essaging System configuration<br>Value |          |           |
| 1   | Signature Block  |  | <b></b>  |           |
| 2   | Keystore File Name   | /keystore                              | =        |           |
| 3   | Keystore Alias name  | ystore Alias name •••••                |          |           |
| А   | Kovetore Roceword  |  | •        |           |
|   | Exit Log   |  | (        | Back Next |

#### 6. Specify the following details:

#### Signature Block

Check this box to enable signature block.

#### **Keystore File Name**

Specify the keystore file name.

#### **Keystore Alias Name**

Specify the keystore alias name.

#### **Keystore Password**

Specify the keystore password.

7. Once you have specified the above details, click 'Next' and system displays the next screen.



## 1.2.7 Saving Property File

After completing all the required settings explained above, you need to save the property file.

1. Save the property file.


| Oracle FLEXCUBE Universal Installer 14.2.0.0.0  | - • <b>X</b>   |
|---|--|
| Oracle Banking Installer  | ORACLE<br>INSTALLER  |
| Property Installation   |  |
| Current screen Displays the status of the property file   |  |
| 2018-11-08T16:48:00,686 DEBUG [AWT-EventQueue-0] com.ofss.installer.common.propertyFile.PropHostOBIB<br>2018-11-08T16:48:00,686 DEBUG [AWT-EventQueue-0] com.ofss.installer.FcubsInstaller: In SetShowPanel: O<br>2018-11-08T16:48:01,365 DEBUG [AWT-EventQueue-0] com.ofss.installer.FcubsInstaller: NextButtonActionPer<br>2018-11-08T16:48:01,365 DEBUG [AWT-EventQueue-0] com.ofss.installer.FcubsInstaller: Screen Name for pro<br>2018-11-08T16:48:01,365 DEBUG [AWT-EventQueue-0] com.ofss.installer.FcubsInstaller: Screen Name for pro<br>2018-11-08T16:48:01,367 DEBUG [AWT-EventQueue-0] com.ofss.installer.fcubs.ubs.PropWebBipFCJ: BIP_EN<br>2018-11-08T16:48:01,367 DEBUG [AWT-EventQueue-0] com.ofss.installer.fcubs.ubs.PropWebBipFCJ: BIP_IN<br>2018-11-08T16:48:01,367 DEBUG [AWT-EventQueue-0] com.ofss.installer.fcubs.ubs.PropWebBipFCJ: BIP_IN<br>2018-11-08T16:48:01,368 DEBUG [AWT-EventQueue-0] com.ofss.installer.fcubs.ubs.PropWebBipFCJ: BIP_SE<br>2018-11-08T16:48:01,368 DEBUG [AWT-EventQueue-0] com.ofss.installer.fcubs.ubs.PropWebBipFCJ: BIP_SE<br>2018-11-08T16:48:01,368 DEBUG [AWT-EventQueue-0] com.ofss.installer.fcubs.ubs.PropWebBipFCJ: BIP_SE<br>2018-11-08T16:48:01,368 DEBUG [AWT-EventQueue-0] com.ofss.installer.fcubs.ubs.PropWebBipFCJ: BIP_SE<br>2018-11-08T16:48:01,369 DEBUG | b) alrea         rformed         ocess o         dy exist         ND_POI         AMESPA         SERNAI         RTS_SP         E_TYPE         ERVER_         ME_ZON         s()>se         ess dell         ad of Ne         s with : ( |
|   | <b>F</b>   |
| View Property File  | Save   |
|   |  |
|   |  |
| Exit Log Back   | Home   |

2. You can view the status of property file creation in the above screen. Once the file is saved, the installer displays the following message:

| Message | • 🛛 🔀                            |
|---------|----------------------------------|
| i       | Property File saved successfully |
|         | ОК                               |



3. If you do not use the 'Save' or Save As' buttons, the installer will save the properties file in '<InstallerSources>\config\PropertyFiles' folder. In that case, you will see the message below.



This completes the properties file creation.





Standalone Scheduler Property File Creation [June] [2024] Version 14.7.4.0.0

Oracle Financial Services Software Limited Oracle Park Off Western Express Highway Goregaon (East) Mumbai, Maharashtra 400 063 India

Worldwide Inquiries: Phone: +91 22 6718 3000 Fax:+91 22 6718 3001 www.oracle.com/financialservices/

Copyright © 2017,2024 Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.