

Oracle® Communications Diameter Signaling Router

Diameter Custom Applications User Guide



Release 9.2.0.0.0
G44913-01
October 2025

ORACLE®

Copyright © 2016, 2025, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

1 Introduction

1.1	Understanding DCA	1
1.2	Intended Scope and Audience	1
1.3	Manual Organization	1
1.4	My Oracle Support	1

2 Activation and Deactivation of DCA

2.1	DCA Activation	1
2.1.1	Activating the DCA Framework	1
2.1.2	Post Framework Activation	3
2.1.3	Activating a DCA Application	4
2.1.4	Post Application Activation	9
2.1.5	Post-Activation DCA Application State	10
2.2	DCA Deactivation	10
2.2.1	Deactivating a DCA Application	10
2.2.2	Post Application Deactivation	14
2.2.3	Deactivating the DCA Framework	14
2.2.4	Post Framework Deactivation	17

List of Figures

2-1	<u>DCA Framework Menu</u>	<u>4</u>
2-2	<u>DCA KPIs</u>	<u>4</u>
2-3	<u>DCA Measurements</u>	<u>4</u>
2-4	<u>DCA Application Menu</u>	<u>10</u>

Preface

- [Documentation Accessibility](#)
- [Diversity and Inclusion](#)
- [Conventions](#)

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customer access to and use of Oracle support services will be pursuant to the terms and conditions specified in their Oracle order for the applicable services.

Diversity and Inclusion

Oracle is fully committed to diversity and inclusion. Oracle respects and values having a diverse workforce that increases thought leadership and innovation. As part of our initiative to build a more inclusive culture that positively impacts our employees, customers, and partners, we are working to remove insensitive terms from our products and documentation. We are also mindful of the necessity to maintain compatibility with our customers' existing technologies and the need to ensure continuity of service as Oracle's offerings and industry standards evolve. Because of these technical constraints, our effort to remove insensitive terms is ongoing and will take time and external cooperation.

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

My Oracle Support

My Oracle Support (<https://support.oracle.com>) is your initial point of contact for all product support and training needs. A representative at Customer Access Support can assist you with My Oracle Support registration.

Call the Customer Access Support main number at 1-800-223-1711 (toll-free in the US), or call the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. When calling, make the selections in the sequence shown below on the Support telephone menu:

1. Select **2** for New Service Request
2. Select **3** for Hardware, Networking and Solaris Operating System Support
3. Select one of the following options:
 - For Technical issues such as creating a new Service Request (SR), select **1**
 - For Non-technical issues such as registration or assistance with My Oracle Support, select **2**

You are connected to a live agent who can assist you with My Oracle Support registration and opening a support ticket.

My Oracle Support is available 24 hours a day, 7 days a week, 365 days a year.

What's New in This Guide

This section introduces the documentation updates for Release 9.2.0.0.0.

Release 9.2.0.0.0 - G44913-01, October 2025

There are no updates to this guide in this release.

1

Introduction

This section contains an overview of the available information for the Diameter Custom Applications (DCA) feature. The contents include sections on the organization, scope, and audience of the documentation, as well how to receive customer support assistance.

1.1 Understanding DCA

The Diameter Custom Applications (DCA) framework allows for the creation of applications on top of the Diameter Signaling Router (DSR), allowing for a faster development cycle.

DCA requires several elements to function:

- An interface that interprets a scripting language in order to manage the receipt of Diameter messages or UDR query results
- An interface that performs basic routing functions such as selecting an Application Route Table or Peer Route Table, forwarding or dropping a Diameter message, or sending a Diameter Answer
- An infrastructure to manage the DCA's business logic and the DCA application's configuration and to generate the script to be used by the interpreting interface

1.2 Intended Scope and Audience

This content is intended for personnel who plan to provision DCA.

This content does not describe how to install or replace software or hardware.

1.3 Manual Organization

This document is organized into the following chapters:

- [Introduction](#) contains general information about DCA, including overview and logic information, the organization of this content, and how to get technical assistance.
- [Activation and Deactivation of DCA](#) provides information about activating and deactivating DCA.

1.4 My Oracle Support

My Oracle Support (<https://support.oracle.com>) is your initial point of contact for all product support and training needs. A representative at Customer Access Support can assist you with My Oracle Support registration.

Call the Customer Access Support main number at 1-800-223-1711 (toll-free in the US), or call the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. When calling, make the selections in the sequence shown below on the Support telephone menu:

1. Select **2** for New Service Request

2. Select **3** for Hardware, Networking and Solaris Operating System Support
3. Select one of the following options:
 - For Technical issues such as creating a new Service Request (SR), select **1**
 - For Non-technical issues such as registration or assistance with My Oracle Support, select **2**

You are connected to a live agent who can assist you with My Oracle Support registration and opening a support ticket.

My Oracle Support is available 24 hours a day, 7 days a week, 365 days a year.

2

Activation and Deactivation of DCA

This chapter provides basic descriptions for activating and deactivating the DCA Framework and DCA applications.

2.1 DCA Activation

In order to use new applications for **DCA**, the DCA Framework must be activated on the NO. Activation needs to be performed only once.

Once developed, a new application then must be activated on the NO. Activation needs to be performed once per application.

① Note

There may be limits on the number of DCA applications that can be simultaneously activated. Old DCA applications may need to be deactivated in order to make room for new applications.

2.1.1 Activating the DCA Framework

This procedure is used to activate the DCA Framework.

1. Log out of any active NOAM GUI sessions.
2. Use an SSH client to connect to the server as **admusr**.

```
# ssh <active NOAM XMI IP Address>
```

3. Change to the feature activation directory.

```
# cd /usr/TKLC/dsr/prod/maint/loaders/
```

4. Execute the feature activation script.

```
# ./featureActivateDeactivate
```

- a. Choose the **Activate** and **DCA Framework** options.
- b. There is an option to choose to activate this feature on all SOAMs or on a specific SOAM.

If a new site is added or if, on some site, framework was not activated, the activation script can be executed again to add the application on new sites. The script won't have any impact on the sites on which the framework is already active.

- c. Verify that the screen output is similar to:

```
[admusr@HPC07-N01 loaders]$ ./featureActivateDeactivate
Tue Feb  2 17:47:18 EST 2016::Starting featureActivateDeactivate main...
Start the Automation script , To run the Feature Activation/
DeActivation on Active NO.
```

You want to Activate or Deactivate the Feature :

- 1.Activate
- 2.Deactivate

Enter your choice : 1

List of Feature you can Activate :

- 1.RBAR
- 2.FABR
- 3.Mediation
- 4.LoadGen
- 5.GLA
- 6.MAP Interworking
- 7.DTLS
- 8.Dca Framework
- 9.Dca Application

Enter the choice : 8

Run script to Activate DcaFramework Feature

```
=====S-T-A-R-
T=====
```

```
=====
=====
```

Execution of Activation/Deactivation Process Starts

```
=====
=====
```

Starting Activation/Deactivation process....

Executing /usr/TKLC/dsr/prod/maint/loaders/activate/
load.DcaFrameworkActivateAsourced script on HPC07-N01

```
=====
=====
```

Current server is HA ACTIVE

```
=====
=====
```

```
=====
=====
```

Add Dca Framework KPI group

```
=====
=====
```

KPI_Group=Dca Framework

Visibility=VIS_ALL

```
=====
=====
```

```
=====
=====
```

Add Dca Framework Measurement groups

```
=====
=====
```

Meas_Group=Dca Framework Performance

Visibility=VIS_ALL

```
=====
=====
```

```
=====
=====
```

Add Dca Framework GUI Configuration Permissions.

```

=====
=====
=====
=====
Set Dca Framework Entry in the DcaFrmEngOption table
=====
=====
=== changed 1 records ===
=====
=====
There is no Standby NOAMP server configured in the Topology
=====
=====
=====
=====
The Active S0 server configured in the Topology are
=====
=====
1. HPC07-S01
2. ALL S0s

Enter your choice on which S0 you want to Activate or Deactivate the
Feature :2
Activate/Deactivate DcaFramework on all S0s configured in the Topology

=====
=====
This is a 3 Tier Setup , So run the B sourced loaders on S0 server :
HPC07-S01
Executing /usr/TKLC/dsr/prod/maint/loaders/activate/
load.DcaFrameworkActivateB sourced script on HPC07-S01
FIPS integrity verification test failed.
Add Dca Framework GUI Configuration Permissions.
FIPS integrity verification test failed.
=====
=====
Executing the Loaders and Clearing Cache on Standby S0 servers.
=====
=====
=====
=====
There is no Standby/Spare SOAMP server configured in the Topology
=====
=====


```

5. Log into the Active NOAM and SOAM GUI.
6. Verify that DCA Framework appears as a menu item on the NOAM and SOAM.
7. Log out of the NOAM login shells using the # exit command and close the SSH connections.

2.1.2 Post Framework Activation

Once the DCA Framework is activated, the **DCA Framework** folder and **Configuration** file becomes visible on the left hand menu as shown in [Figure 2-1](#).

Figure 2-1 DCA Framework Menu



All the KPIs and measurements associated with the DCA Framework also become visible as shown in [Figure 2-2](#) and [Figure 2-3](#) respectively.

Figure 2-2 DCA KPIs

Main Menu: Status & Manage -> KPIs

Filter Tasks

Tue May 03 06:37:40 2016

Entire Network	Gremlin-DAMP-1	Gremlin-DAMP-2	Gremlin-DAMP-3	Gremlin-DAMP-4	Gremlin-NO-A	Gremlin-NO-B	Gremlin-SO1-A	Gremlin-SO1-B	Gremlin-SO2-A
ComAgent	DCA Framework	Server							
Name	Max	Min	Median	Average	Sum	Description			
Ingress Message Rate	0.00	0.00	0.00	0.00	0.00	Average Ingress Message Rate (messages per second) of Diameter messages received by the DCA Application.			
Runtime Errors Rate	0.00	0.00	0.00	0.00	0.00	Instant Runtime Error Rate (runtime errors per second during the last sampling interval)			
Completed Transactions	0.00	0.00	0.00	0.00	0.00	Diameter transactions that a DCA App successfully relays			
Transactions Discard Request	0.00	0.00	0.00	0.00	0.00	Allows the operator to determine how many transactions a DCA app relay terminates by discarding the request (by comparison with the Completed Transactions).			

Figure 2-3 DCA Measurements

Main Menu: Measurements -> Report

Filter Info Tasks

Filter

Scope: - Network Element - - Server Group - Reset

Report: DCA Framework Exception -- Interval -- Reset

Column Filter: -- Group -- ComAgent Exception ComAgent Performance DCA Framework Exception DCA Framework Performance IDIH OAM.ALARM OAM.SYSTEM Server Exception Reset

Time Range: 2016 Jan 01 00 00 Reset

Go

2.1.3 Activating a DCA Application

This procedure is used to activate a DCA application.

1. Log out of any active NOAM GUI sessions.
2. Use an SSH client to connect to the server as **admusr**.
ssh <active NOAM XMI IP Address>
3. Change to the feature activation directory.
cd /usr/TKLC/dsr/prod/maint/loaders/
4. Execute the feature activation script.
./featureActivateDeactivate
 - a. Choose **Activate** and **DCA Application**.
 - b. Enter a long name for the new application when prompted.

Note

The DCA application long name consists of a combination of letters, numbers, and spaces. It can't begin with a space and has a maximum of 32 characters.

- c. Enter a short name for the application when prompted.

Note

The DCA application short name consists of a combination of letters and numbers. It has a maximum of 6 characters.

- d. Verify that the screen output is similar to:

```
[admusr@HPC07-N01 loaders]$ ./featureActivateDeactivate
Tue Feb  2 17:52:59 EST 2016::Starting featureActivateDeactivate main...
Start the Automation script , To run the Feature Activation/
DeActivation on Active NO.
```

You want to Activate or Deactivate the Feature :

- 1.Activate
- 2.Deactivate

Enter your choice : 1

List of Feature you can Activate :

- 1.RBAR
- 2.FABR
- 3.Mediation
- 4.LoadGen
- 5.GLA
- 6.MAP Interworking
- 7.DTLS
- 8.Dca Framework
- 9.Dca Application

Enter the choice : 9

```
===== Start of Log Data in file /var/TKLC/log/
DcaActivationTopLevel.log =====
```

```
=====S-T-A-R-
T=====
```

Log file location: /var/TKLC/log/DcaActivationTopLevel.log

Note:-

In case of any failure please execute /usr/TKLC/dsr/prod/maint/loaders/deactivate/load.DcaDeactivationTopLevel script to revert the changes.

```
=====
=====
Execution of Activation Process Starts
=====
=====
Dca framework is activated on the setup..Continuing
Following Dca apps are activated on the system:
First Dca App
Enter the long name for the Dca application:Second DCA App
Entered dca name Second DCA App consist of valid characters
Entered Name is Second DCA App
next available dal id is 129
Enter the short name for the Dca application:sda
length of shortName is 3.continuing..
Entered dca name sda consist of valid characters
Entered Name is sda
=====
Verify that Dca Application is in the DalId table
=====
dalId=129
birthTime=02/02/2016 17:53:22.000
name=Second DCA App
shortName=sda
activated=No
=====
=====
Verify that Dca Application is in the DcaDalId table
=====
dalId=129
name=Second DCA App
shortName=sda
=====
Executing /usr/TKLC/dsr/prod/maint/loaders/activate/
load.DcaActivateAscped script on HPC07-N01

===== Start of Log Data in file /var/TKLC/log/
DcaActivateAscped.log =====

Server Name   : HPC07-N01
Server Role   : NETWORK_OAMP
Node Id       : HPC07-N01
HA State      : Active
Cluster Role  : Primary
=====
Add Dca application entry to the DsrApplication table.
```

```

=====
=====
Verify that Dca Application is in the table
=====
id=129
name=sda
unavailableAction=ContinueRouting
avpInsertion=Yes
shutdownMode=Graceful
shutdownTimer=5
resultCode=3002
vendorId=0
errorString=Dca Application Unavailable Or Degraded
resExhResultCode=3004
resExhVendorId=0
resExhErrorString=Dca Resource Exhausted
routeListId=-1
realm=
fqdn=
mcl=0
=====
=====
Add Dca Application KPI group
=====
=====
Add Dca Application Measurement groups
=====
=====
Add Permission Group headers for Dca Application
=====
=====
Add network configuration parameters for Dca
=====

=====E-N-
D=====

Execution status of activation script on HPC07-N01: PASSED
Please check /var/TKLC/log/DcaActivateAscoped.log for more details.

=====
=====
Starting Activation on StandBy NOAMP Server if it exists in the
topology.

HPC07-N01 is Active and Primary NOAMP Server. So, proceeding with next
NOAMP Server.
===== Activation done on all Network OAMP Servers =====

===== Starting Activation on System OAM servers =====

=====
=====
HPC07-S01 is Active. So, proceeding with Activation.
FIPS integrity verification test failed.
Executing /usr/TKLC/dsr/prod/maint/loaders/activate/

```

load.DcaActivateBscoped script on HPC07-S01
FIPS integrity verification test failed.

===== Start of Log Data in file /var/TKLC/log/
DcaActivateBscoped.log =====

Server Name : HPC07-S01
Server Role: SYSTEM_OAM
Node Id : HPC07-S01
HA State : Active

=====

Add Dca application to DsrApplication. If already present then skip.

=====

Verify that Dca application is in the table

=====

id=129
name=sda
unavailableAction=ContinueRouting
avpInsertion=Yes
shutdownMode=Graceful
shutdownTimer=5
resultCode=3002
vendorId=0
errorString=
resExhResultCode=3004
resExhVendorId=0
resExhErrorString=Dca Resource Exhausted
routeListId=-1
realm=
fqdn=
mcl=0

=====

=====

Add Permission Group headers for Dca app on SOAM server

=====

Add system configuration parameters for Dca

=====

=====END=====

=====

Execution status of activation script on HPC07-S01: PASSED
Please check /var/TKLC/log/DcaActivateBscoped.log.HPC07-S01 for more
details.

FIPS integrity verification test failed.
FIPS integrity verification test failed.

=====

=====

=== changed 1 records ===

=====

Verify that activated field is updated for Dca Application in the DalId
table

=====

dalId=129
birthTime=02/02/2016 17:53:22.000

```

name=Second DCA App
shortName=sda
activated=Yes
=====
=====
=====
Execution of Dca Applicaion Activation Script complete.
=====
=====
=====E-N-
D=====


```

- e. Restart the DSR MP from **Main Menu**, and then **Status & Manage**, and then **Server**.
5. Log into an Active NOAM and SOAM GUI.
6. Verify that DCA Application folder appears under the DCA Framework menu item on an NOAM and SOAM.
 - a. Verify that the folder for the new DCA application appears under DCA Framework on an NOAM. Under the application folder has General Options, Trial MP assignment, and Application Control sub-options.
 - b. Verify that the folder for the new DCA application appears under DCA Framework on an SOAM. Under the application folder has General Options, Trial MP assignment, and Application Controll, and System Options sub-options.
7. Log out of the NOAM login shells using the `# exit` command and close the SSH connections.

2.1.4 Post Application Activation

When the new DCA application is activated, the application subfolder with the name provided by the user during the activation procedure becomes visible on the left side menu as shown in [Figure 2-4](#). The application subfolder includes the pages for enabling the business logic and provisioning configuration data. The application becomes visible across DSR. For further details on a specific application, refer to the user's guide for that specific application.

Figure 2-4 DCA Application Menu



2.1.5 Post-Activation DCA Application State

After activation, a DCA application is in the disabled state. While in the disabled state, Diameter traffic is not delivered to the application. The application must be enabled from **Diameter**, and then **Maintenance**, and then **Applications**. The application is identified by the name configured by the user during the activation of the application.

Regardless of whether or not a DCA application is enabled or disabled, no version of the application is provisioned. No version is in the production or trial state. As long as no production or trial version is available for a **DA-MP** to run, the application's operational status is unavailable (see **Diameter**, and then **Maintenance**, and then **Applications** on the SO). An Application Route Table (**ART**) must also be defined for the new application (see **Diameter**, and then **Configuration**, and then **Application Route Tables**).

Afterward, the configuration and business logic for the DCA application are provisioned.

2.2 DCA Deactivation

To deactivate DCA, an application and the DCA Framework must be removed.

2.2.1 Deactivating a DCA Application

This procedure is used to deactivate a DCA application.

1. Log out of any active NOAM GUI sessions.
2. Use an SSH client to connect to the server as **admusr**.
ssh <active NO XMI IP Address>
3. Change to the feature deactivation directory.

```
# cd /usr/TKLC/dsr/prod/maint/loaders/
```

4. Execute the feature activation script.

```
# ./featureActivateDeactivate
```

- a. Choose **Deactivate** and **DCA Application**.
- b. Enter the name for the application to be deactivated when prompted.
- c. Verify that the screen output is similar to:

```
[admsr@HPC07-N01 loaders]$ pwd
/usr/TKLC/dsr/prod/maint/loaders
[admsr@HPC07-N01 loaders]$ ./featureActivateDeactivate
Tue Feb  2 17:59:21 EST 2016::Starting featureActivateDeactivate main...
Start the Automation script , To run the Feature Activation/
DeActivation on Active NO.
```

```
You want to Activate or Deactivate the Feature :
1.Activate
2.Deactivate
```

```
Enter your choice : 2
```

```
Which Feature you want to Deactivate :
1.RBAR
2.FABR
3.Mediation
4.LoadGen
5.GLA
6.MAP Interworking
7.DTLS
8.Dca Framework
9.Dca Application
```

```
Enter your choice : 9
```

```
===== S-T-A-R-T of log
DcaDeactivationTopLevel.log =====
Log file location: /var/TKLC/log/DcaDeactivationTopLevel.log
=====
=====Execution of Deactivation Process Starts
=====
=====Following Dca apps are activated on the system
1. FDA
2. sda
Enter the name for the Dca application to be deactivated:sda
The name of application selected to deactivate is: sda
=== changed 1 records ===
=====
DalId Table successfully updated with deactivated status.
=====

=====
=====
HPC07-S01 is Active. So, proceeding with Deactivation.
FIPS integrity verification test failed.
```

```

Executing /usr/TKLC/dsr/prod/maint/loaders/deactivate/
load.DcaDeactivateBscoped script on HPC07-S01
FIPS integrity verification test failed.

```

```

===== Start of Log Data in file /var/TKLC/log/
DcaDeactivateBscoped.log =====

```

```

Server Name : HPC07-S01
Server Role: SYSTEM_OAM
Node Id    : HPC07-S01
HA State   : Active

```

```

=====
Remove the ART rules corresponding to the DCA
=====

```

```

No rules configured for the current application.
=====

```

```

Remove Dca from DcaAppSystemUserOption table
=====

```

```

=== deleted 5 records ===

```

```

Remove Dca Application from DsrApplicationPerMp table
=====

```

```

=== deleted 0 records ===

```

```

Remove Dca Application from DsrApplication table
=====

```

```

=== deleted 1 records ===

```

```

Remove permission group headers for Dca Application on SOAM server
=====

```

```

=== deleted 1 records ===

```

```

=====END=====
=====

```

```

Execution status of deactivation script on HPC07-S01: PASSED
Please check /var/TKLC/log/DcaDeactivateBscoped.log.HPC07-S01 for more
details.

```

```

FIPS integrity verification test failed.

```

```

FIPS integrity verification test failed.

```

```

=====
=====

```

```

=====
=====

```

```

Starting Deactivation on Standby NOAMP server if present in topology.
=====

```

```

=====

```

```

HPC07-N01 is Active NOAMP Server. Proceeding with next NOAMP server in
the list.

```

```

=====
=====

```

```

Starting Deactivation on Active NOAMP server.
=====

```

```

=====

```

Executing /usr/TKLC/dsr/prod/maint/loaders/deactivate/
load.DcaDeactivateAscoped script on HPC07-N01

===== Start of Log Data in file /var/TKLC/log/
DcaDeactivateAscoped.log =====

Server Name : HPC07-N01
Server Role : NETWORK_OAMP
Node Id : HPC07-N01
HA State : Active
Cluster Role : Primary

=====

Remove Dca Application KPI groups

=====

=== deleted 1 records ===

=====

Remove Dca Application Measurement groups

=====

=== deleted 1 records ===

=====

Remove permission group headers for Dca Application

=====

=== deleted 1 records ===

=====

Remove logical to physical udr db mapping from
DcaLog2PhyUdr and DcaLogicalUdr table

=====

=====

Remove Dca from DcaLifecycleNoam table

=====

=== deleted 0 records ===

=====

Remove Dca from DcaAppNetworkUserOption table

=====

=== deleted 3 records ===

=====

Remove Dca from DcaTrialMp table

=====

=== deleted 0 records ===

=====

Remove Dca from DsrApplicationPerMp table

=====

=== deleted 0 records ===

=====

Remove Dca Application from DsrApplication table

=====

=== deleted 1 records ===

=== deleted 1 records ===

=== deleted 1 records ===

=====END=====

=====

Execution status of deactivation script on HPC07-N01: PASSED

=====

=====Execution of Dca Application Deactivation Script complete.

```
=====
=====
=====E-N-
D=====
```

- d. Restart the DSR MP from **Main Menu**, and then **Status & Manage**, and then **Server**.
5. Log into an Active NOAM and SOAM GUI.
6. Verify that the specific DCA application folder disappears as a menu item on the NOAM and SOAM..
7. Log out of the NOAM login shells using the `# exit` command and close the SSH connections.

2.2.2 Post Application Deactivation

Deactivating a DCA application is not allowed as long as versions of the the application are still in the production and/or trial states.

After deactivation, the application's GUI fold under the **DCA Framework** menu item disappears. The application is deregistered from the ART, its KPIs and measurements are no longer displayed, and are no longer reported.

2.2.3 Deactivating the DCA Framework

This procedure is used to deactivate the DCA Framework.

1. Log out of any active NOAM GUI sessions.
2. Use an SSH client to connect to the server as **admusr**.
ssh <active NO XMI IP Address>
3. Change to the feature deactivation directory.
cd /usr/TKLC/dsr/prod/maint/loaders/
4. Execute the feature activation script.
./featureActivateDeactivate
 - a. Choose the **Deactivate** and **DCA Framework** options.
 - b. For 3-Tiered Architecture, you can deactivate this feature on all SOAMs or on a specific SOAM
 - c. Verify that the screen output is similar to:

```
[admusr@HPC07-N01 loaders]$ pwd
/usr/TKLC/dsr/prod/maint/loaders
[admusr@HPC07-N01 loaders]$ ./featureActivateDeactivate
Tue Feb  2 17:59:21 EST 2016::Starting featureActivateDeactivate main...
Start the Automation script , To run the Feature Activation/
DeActivation on Active NO.
```

```
You want to Activate or Deactivate the Feature :
1.Activate
2.Deactivate
```

```
Enter your choice : 2
```

Which Feature you want to Deactivate :

- 1.RBAR
- 2.FABR
- 3.Mediation
- 4.LoadGen
- 5.GLA
- 6.MAP Interworking
- 7.DTLS
- 8.Dca Framework
- 9.Dca Application

Enter your choice : 9

===== S-T-A-R-T of log

DcaDeactivationTopLevel.log =====

Log file location: /var/TKLC/log/DcaDeactivationTopLevel.log

=====

=====Execution of Deactivation Process Starts

=====

=====Following Dca apps are activated on the system

1. FDA
2. sda

Enter the name for the Dca application to be deactivated:sda

The name of application selected to deactivate is: sda

=== changed 1 records ===

=====

DalId Table successfully updated with deactivated status.

=====

=====

=====

HPC07-S01 is Active. So, proceeding with Deactivation.

FIPS integrity verification test failed.

Executing /usr/TKLC/dsr/prod/maint/loaders/deactivate/

load.DcaDeactivateBscoped script on HPC07-S01

FIPS integrity verification test failed.

===== Start of Log Data in file /var/TKLC/log/

DcaDeactivateBscoped.log =====

Server Name : HPC07-S01

Server Role: SYSTEM_OAM

Node Id : HPC07-S01

HA State : Active

=====

Remove the ART rules corresponding to the DCA

=====

No rules configured for the current application.

=====

Remove Dca from DcaAppSystemUserOption table

=====

=== deleted 5 records ===

=====

Remove Dca Application from DsrApplicationPerMp table

=====

=== deleted 0 records ===

```

=====
Remove Dca Application from DsrApplication table
=====
=== deleted 1 records ===
=====
Remove permission group headers for Dca Application on SOAM server
=====
=== deleted 1 records ===
=====END=====
=====

Execution status of deactivation script on HPC07-S01: PASSED
Please check /var/TKLC/log/DcaDeactivateBscoped.log.HPC07-S01 for more
details.
FIPS integrity verification test failed.
FIPS integrity verification test failed.
=====
=====

=====
=====
Starting Deactivation on Standby NOAMP server if present in topology.
=====
=====

HPC07-N01 is Active NOAMP Server. Proceeding with next NOAMP server in
the list.

=====
=====
Starting Deactivation on Active NOAMP server.
=====
=====

Executing /usr/TKLC/dsr/prod/maint/loaders/deactivate/
load.DcaDeactivateAsscoped script on HPC07-N01

===== Start of Log Data in file /var/TKLC/log/
DcaDeactivateAsscoped.log =====

Server Name   : HPC07-N01
Server Role   : NETWORK_OAMP
Node Id       : HPC07-N01
HA State      : Active
Cluster Role  : Primary
=====
Remove Dca Application KPI groups
=====
=== deleted 1 records ===
=====
Remove Dca Application Measurement groups
=====
=== deleted 1 records ===
=====
Remove permission group headers for Dca Application
=====

```

```

=== deleted 1 records ===
=====
Remove logical to physical udr db mapping from
DcaLog2PhyUdr and DcaLogicalUdr table
=====
Remove Dca from DcaLifecycleNoam table
=====
=== deleted 0 records ===
=====
Remove Dca from DcaAppNetworkUserOption table
=====
=== deleted 3 records ===
=====
Remove Dca from DcaTrialMp table
=====
=== deleted 0 records ===
=====
Remove Dca from DsrApplicationPerMp table
=====
=== deleted 0 records ===
=====
Remove Dca Application from DsrApplication table
=====
=== deleted 1 records ===
=== deleted 1 records ===
=== deleted 1 records ===
=====END=====
=====

Execution status of deactivation script on HPC07-N01: PASSED
=====
=====Execution of Dca Application Deactivation Script complete.
=====
=====
=====E-N-
D=====

```

5. Log into an Active NOAM and SOAM GUI.
6. Verify that DCA Framework disappears as a menu item on the NOAM and SOAM.
7. Log out of the NOAM login shells using the # exit command and close the SSH connections.

2.2.4 Post Framework Deactivation

Deactivating the DCA Framework is not allowed as long as at least one DCA application is activated in the network.

Following deactivation, the **DCA Framework** GUI folder disappears from the left hand menu.