

**Oracle® Communications
User Data Repository
Cloud Disaster Recovery Guide
Release 15.1
G61301-01**

August 2026

ORACLE®

Oracle Communications User Data Repository Cloud Disaster Recovery Guide, Release 15.1

G61301-01

Copyright © 2016, 2017, 2018, 2023, 2026 Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.



CAUTION: Open an Service Request on MOS and confer with Oracle before executing Disaster Recovery Procedure

Before recovering any system, please access My Oracle Support (MOS) (<https://support.oracle.com>) and review any MOS Alerts that relate to this procedure.

My Oracle Support (MOS) (<https://support.oracle.com>) is your initial point of contact for all product support and training needs. A representative at Customer Access Support (CAS) can assist you with MOS registration.

Call the CAS main number at 1-800-223-1711 (toll-free in the US), or call the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>.

See more information on MOS in the Appendix section.

TABLE OF CONTENTS

1	INTRODUCTION	5
1.1	Purpose and Scope.....	5
1.2	References	5
1.3	Acronyms.....	6
1.4	Terminology	6
1.5	How to Use this Document.....	7
2	GENERAL DESCRIPTION	8
2.1	Complete Site Outage (All Servers)	8
2.2	Partial outage with one NOAMP server intact and both SOAMs failed	8
2.3	Partial outage with both NOAMP servers failed and one SOAM server intact.....	8
2.4	Partial outage with NOAMP and one SOAM server intact	9
2.5	Partial outage with Corrupt Database.....	9
3	PROCEDURE OVERVIEW.....	10
3.1	Required Materials	10
3.2	Disaster Recovery Strategy.....	11
3.3	Procedure Preparation	12
4	DISASTER RECOVERY PROCEDURE	14
4.1	Recovering and Restoring System Configuration	15
4.1.1	Recovery Scenario 1 (Complete Site Outage).....	15
4.1.2	Recovery Scenario 2 (Partial Server Outage with one NOAMP server intact and both SOAMs failed).....	41
4.1.3	Recovery Scenario 3 (Partial Server Outage with all NOAMP servers failed and one SOAM server intact)	63
4.1.4	Recovery Scenario 4 (Partial Server Outage with one NOAMP server and one SOAM server intact).....	80
4.1.5	Recovery Scenario 5 (Database Recovery).....	94
5	RESOLVING USER CREDENTIAL ISSUES AFTER DATABASE RESTORE.....	99
5.1	Keeping a Restored User (Resetting User Password).....	99
5.2	Removing a Restored User	101
5.3	Restoring a Modified User.....	102
5.4	Restoring an Archive that does not contain a Current User	103
Appendix A.	Oracle Communications User Data Repository Database Backup.....	107
Appendix B.	Inhibit A and B Level Replication on C-Level Servers.....	111

Appendix C. Un-Inhibit A and B Level Replication on C-Level Servers 113

Appendix D. My Oracle Support (MOS)..... 115

Appendix E. Locate Product Documentation on the Oracle Help Center Site 116

List of Figures

Figure 1. Determining Recovery Scenario 11

List of Tables

Table 1. Terminology.....6

Table 2: Recovery Scenarios..... 12

1 INTRODUCTION

1.1 Purpose and Scope

This document describes disaster recovery procedures used during disaster scenarios of the cloud based Oracle Communications User Data Repository 15.0 product.

This document is a guide to describe procedures used to execute disaster recovery for Oracle Communications User Data Repository Cloud deployments. This includes recovery of partial or a complete loss of one or more Oracle Communications User Data Repository virtual servers (Primary or DR). The audience for this document includes Oracle customers as well as the following internal groups: Software Development, Quality Assurance, Product Verification, Information Development, and Consulting Services including NPx.. This document provides step-by-step instructions to execute disaster recovery for Oracle Communications User Data Repository 15.0. Executing this procedure also involves referring to and executing procedures in existing support documents found in the reference section.

This document is intended for execution by Customer Service team on the fielded Oracle Communications User Data Repository 15.0 systems.

1.2 References

- [1] *Oracle Communications User Data Repository 12.11 Disaster Recovery Guide*, E83400-01, latest revision
- [2] *Oracle Communications User Data Repository 12.11 Cloud Installation and Configuration Guide*, latest revision

1.3 Acronyms

Acronym	Meaning
BIOS	Basic Input Output System
CD	Compact Disk
DR	Disaster Recovery
FRU	Field Replaceable Unit
IMI	Internal Management Interface
ISL	Inter-Switch-Link
NE	Network Element
MP Host Server	Server that contains one SOAM and two MPs
NOAMP	Network Operations, Administration, Maintenance & Provisioning
ISO	Constains software images
OVA	Open Virtualization Archive
MOS	My Oracle Support
NAPD	Network Architecture Planning Diagram
SOAM	Systems Operations, Administration & Maintenance
TAC	Technical Assistance Centers
TPD	Tekelec Platform Distribution (Linux OS)
UDR	User Data Repository
VIP	Virtual IP
VM	Virtual Machine
XMI	External Management Interface

1.4 Terminology

Table 1. Terminology

Base hardware	Base hardware includes all hardware components (bare metal) and electrical wiring to allow a server to power on.
Base software	Base software includes installing the server's operating system: Tekelec Platform Distribution (TPD) and TVOE for the MP Host Servers only.
Failed server	A failed server in disaster recovery context refers to a server that has suffered partial or complete software and/or hardware failure to the extent that it cannot restart or be returned to normal operation and requires intrusive activities to re-install the software and/or hardware.

Enablement	The business practice of providing support services (hardware, software, documentation, etc) that enable a 3 rd party entity to install, configuration, and maintain Oracle products for Oracle customers.
Software Centric	The business practice of delivering an Oracle software product, while relying upon the customer to procure the requisite hardware components. Oracle provides the hardware specifications, but does not provide the hardware, and is not responsible for hardware installation, configuration, or maintenance.

1.5 How to Use this Document

When executing this document, understanding the following helps to ensure that the user understands the manual's intent:

- Before beginning a procedure, completely read the instructional text (it appears immediately after the Section heading for each procedure) and all associated procedural WARNINGS or NOTES.
- Before execution of a STEP within a procedure, completely read the left and right columns including any STEP specific WARNINGS and/or NOTES.

If a procedural STEP fails to execute successfully, please STOP and contact My Oracle Support (MOS).

2 GENERAL DESCRIPTION

Disaster recovery procedures falls into five basic categories. It is primarily dependent on the state of the NOAMP servers and SOAM servers:

Recovery of the entire site from a total outage	• All NOAMP servers failed • All SOAM servers failed • 1 or more MP servers failed
Recovery of one or more servers with at least one NOAMP server intact	• 1 or more NOAMP servers intact • 1 or more SOAM or MP servers failed
Recovery of the NOAMP pair with one or more SOAM servers intact	• All NOAMP servers failed • 1 or more SOAM servers intact
Recovery of one or more server with at least one NOAMP and one SOAM server intact.	• 1 or more NOAMP servers intact • 1 or more SOAM servers intact • 1 SOAM or 1 or more MP servers failed
Recovery of one or more servers with corrupt database	• Case 1: No Replication Channel • Case 2: Replication Channel Available

2.1 Complete Site Outage (All Servers)

This is the worst case scenario where all the servers in the site have suffered complete software failure. The servers are recovered using OVA images then restoring database backups to the active NOAMP and SOAM servers. Note: NOAMP servers which were originally installed by ISO instead of OVA will be recovered using ISO.

Database backups will be taken from customer offsite backup storage locations (assuming these were performed and stored offsite prior to the outage). If no backup files are available, the only option is to rebuild the entire network from scratch. The network data must be reconstructed from whatever sources are available, including entering all data manually.

2.2 Partial outage with one NOAMP server intact and both SOAMs failed

This case assumes that at least one NOAMP servers intact. All SOAM servers have failed and are recovered using OVA images. Database is restored on the SOAM server and replication will recover the database of the remaining servers.

2.3 Partial outage with both NOAMP servers failed and one SOAM server intact

Database is restored on the NOAMP and replication will recover the database of the remaining servers.

2.4 Partial outage with NOAMP and one SOAM server intact

The simplest case of disaster recovery is with at least one NOAMP and at least one SOAM servers intact. All servers are recovered using base recovery of software. Database replication from the active NOAMP and SOAM servers will recover the database to all servers.

2.5 Partial outage with Corrupt Database

Case 1: Database is corrupted, replication channel is inhibited (either manually or because of comcol upgrade barrier) and database backup is available.

Case 2: Database is corrupted but replication channel is available.

3 PROCEDURE OVERVIEW

This section lists the materials required to perform disaster recovery procedures and a general overview (disaster recovery strategy) of the procedure executed.

3.1 Required Materials

The following items are needed for disaster recovery:

1. A hardcopy of this document (E71445-01) and hardcopies of all documents in the reference list
2. Hardcopy of all NAPD performed at the initial installation and network configuration of this customer's site. If the NAPD cannot be found, escalate this issue within My Oracle Support (MOS) until the NAPD documents can be located.
3. Oracle Communications User Data Repository recent backup files: electronic backup file (preferred) or hardcopy of all Oracle Communications User Data Repository configuration and provisioning data.
4. Latest Network Element report: Electronic file or hardcopy of Network Element report.
5. The network element XML file used for the VMs initial configuration.

The software media referenced here may be acquired online from the Oracle e-Delivery service at edelivery.oracle.com

This document and others referenced here can be acquired online from the Oracle Document Repository at the following URL:

<http://docs.oracle.com/en/industries/communications/user-data-repository/index.html>


Note: For all Disaster Recovery scenarios, we assume that the NOAMP Database backup and the SOAM database backup were performed around the same time, and that no synchronization issues exist among them.

3.2 Disaster Recovery Strategy

Disaster recovery procedure execution is performed as part of a disaster recovery strategy with the basic steps listed below:

1. Evaluate failure conditions in the network and determine that normal operations cannot continue without disaster recovery procedures. This means the failure conditions in the network match one of the failure scenarios described in section 2.
2. Read and review the content in this document.
3. Gather required materials in section 3.1 **Required Materials**
4. From the failure conditions, determine the Recovery Scenario and procedure to follow (using Figure 1. Determining Recovery Scenario).
5. Execute appropriate recovery procedures (listed in section 4).

Figure 1. Determining Recovery Scenario



3.3 Procedure Preparation

Disaster recovery procedure execution is dependent on the failure conditions in the network. The severity of the failure determines the recovery scenario for the network. Use Table 2: Recovery Scenarios below to evaluate the correct recovery scenario and follow the procedure(s) listed to restore operations.

Note: A failed server in disaster recovery context refers to a server that has suffered partial or complete software failure to the extent that it cannot restart or be returned to normal operation and requires intrusive activities to re-deploy base software.

Table 2: Recovery Scenarios

Recovery Scenario	Failure Condition	Section
1	- All NOAMP servers failed. - All SOAM servers failed. - MP servers may or may not be failed.	Section Recovery Scenario 1 (Complete Site Outage)
2	- At least 1 NOAMP server is intact and available. - All SOAM servers failed. - MP servers may or may not be failed.	Section Recovery Scenario 2 (Partial Server Outage with one NOAMP server intact and both SOAMs failed)
3	- All NOAMP servers failed. - At least 1 SOAM server is intact and available. - MP servers may or may not be failed.	Section Recovery Scenario 3 (Partial Server Outage with all NOAMP servers failed and one SOAM server intact)
4	- At least 1 NOAMP server is intact and available. - At least 1 SOAM is intact and available. 1 or more MP servers have failed.	Section Recovery Scenario 4 (Partial Server Outage with one NOAMP server and one SOAM server intact)
5	- Server is intact - Database gets corrupted on the server	Section Recovery Scenario 5 (Database Recovery)
5: Case 1	- Server is intact - Database gets corrupted on the server	Section Recovery Scenario 5: Case 1

	• Replication is inhibited (either manually or because of comcol upgrade barrier)	
5: Case 2	• Server is intact • Database gets corrupted on the server • Replication is occurring to the server with corrupted database	Section Recovery Scenario 5: Case 2

4 DISASTER RECOVERY PROCEDURE

Call the CAS main number at **1-800-223-1711** (toll-free in the United States), or call the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html> prior to executing this procedure to ensure that the proper recovery planning is performed.

Before disaster recovery, users must properly evaluate the outage scenario. This check ensures that the correct procedures are executed for the recovery.

****** WARNING *******

****** WARNING *******

Note: *Disaster recovery is an exercise that requires collaboration of multiple groups and is expected to be coordinated by the TAC prime. Based on TAC's assessment of Disaster, it may be necessary to deviate from the documented process.*

4.1 Recovering and Restoring System Configuration

Disaster recovery requires configuring the system as it was before the disaster and restoration of operational information. There are 7 distinct procedures to choose from depending on the type of recovery needed. Only one of these should be followed (not all).

4.1.1 Recovery Scenario 1 (Complete Site Outage)

For a complete server outage, NOAMP servers are recovered using recovery procedures for software and then executing a database restore to the active NOAMP server. All other servers are recovered using recovery procedures for software.

Database replication from the active NOAMP server will recover the database on these servers. The major activities are summarized in the list below. Use this list to understand the recovery procedure summary. Do not use this list to execute the procedure. The actual detailed steps are in . The major activities are summarized as follows:

Recover Base software for all VMs:

- Recover the Virtual Machines hosting the NOAMPs and SOAMs
- Recover the **Active NOAMP** server by recovering the NOAMPs base software
- Recover the NOAMP database
- Reconfigure the application

Recover the **Standby NOAMP** server by recovering base software, for a Non-HA deployment this can be skipped.

- Reconfigure the Oracle Communications User Data Repository Application

Recover all SOAM and MP servers by recovering software, In a Non-HA deployment the Standby SOAM servers can be skipped.

- Recover the SOAM database
- Reconfigure the Oracle Communications User Data Repository Application
- Reconfigure the signaling interface and routes on the MPs, the Oracle Communications User Data Repository software will automatically reconfigure the signaling interface from the recovered database.

Restart process and re-enable provisioning replication

Note: Any other applications DR recovery actions (PCRF, etc) may occur in parallel. These actions can/should be worked simultaneously; doing so would allow faster recovery of the complete solution.

Procedure 1: Recovery Scenario 1 -- Complete Server Outage

S T E P #	This procedure performs recovery if both NOAMP servers are failed and all SOAM servers are failed. This procedure also caters the C-Level Sever failure	Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number. If this procedure fails, contact My Oracle Support (MOS) , and ask for assistance.
1. ☐	Gather Required Materials	Gather the documents and required materials listed in Section Required Materials
2. ☐	Recover the Failed Software	Execute the following procedures from reference <i>Oracle Communications User Data Repository 12.11 Cloud Installation and Configuration Guide, latest revision</i> [2]: Procedure 2 : Deploy Oracle Communications User Data Repository Virtual Machines
4. ☐	Obtain Latest Database Backup and Network Configuration Data.	Obtain the most recent database backup file from external backup sources (ex. file servers) or tape backup sources. From required materials list in Section 3.1 Required Materials ; use site survey documents and Network Element report (if available), to determine network configuration data.
5. ☐	Execute UDR Installation Procedure for the First NOAMP	Configure the First NOAMP server by executing procedures from reference <i>Oracle Communications User Data Repository 12.11 Cloud Installation and Configuration Guide, latest revision</i> [2]: Procedure 3 “Configure NOAMP-A Server (1 st NOAMP Only)” Note: If Topology or nodeId alarms are persistent after the database restore, refer to the steps below.

Procedure 1: Recovery Scenario 1 -- Complete Server Outage


6.	Active NOAMP: Login	Login to the NOAMP GUI as the guiadmin user: 
----	------------------------	--

Procedure 1: Recovery Scenario 1 -- Complete Server Outage

7.

Active NOAMP:
Upload the
Backed up
Database File

Browse to **Main Menu** → **Status & Manage** → **Files**



Select the Active NOAMP server. The following screen will appear:

Cpa1-NO	Cpa1-IPFE	Cpa1-Sbr1	Cpa1-Mp1	Cpa1-Mp2	Cpa1-Mp3	Cpa1-Sbr2
File Name	Size	Type	Timestamp			
Backup.dsr.Cpa1-NO.Configuration.NETWORK_OAMP.20120321_021501.AUTO.tar	720 KB	tar	2012-03-21 06:15:02 UTC			

Click on **Upload** as shown below and select the file “*NO Provisioning and Configuration:*” file backed up after initial installation and provisioning.

Delete

View

Upload

Download

0 used (0%) of 0 available | System utilization: 0 (0%) of 0 available.

Click on **Browse** and locate the backup file and click on Open as shown below.

File:

Browse...

Upload

Cancel

Choose file

Look in: PV3

Backup.EAGLEVPipeCOMProv.tgz

Backup.PV3.tgz

PV3_NetHawk.txt

File name: Backup.PV3.tgz

Files of type: All Files (*.*)

Open

Cancel

Click on the **Upload** button. The file will take a few seconds to upload depending on the size of the backup data. The file will be visible on the list of entries after the upload is complete.



Release 15.1

18

August 2026


Confidential - Oracle Restricted \Employees Only

Procedure 1: Recovery Scenario 1 -- Complete Server Outage


8. ☐	Active NOAMP: Disable Provisioning	Click on Main Menu → Status & Manage → Database A screenshot of a software interface showing a 'Status & Manage' menu. The menu is a vertical list of items: Network Elements, Server, Replication, Collection, HA, Database, KPIs, Processes, and Files. The 'Database' item is highlighted with a dashed border. Disable Provisioning by clicking on Disable Provisioning button at the bottom of the screen as shown below. A screenshot of a row of buttons: 'Disable Provisioning', 'Report...', 'Inhibit/Allow', 'Backup...', 'Compare...', and 'Restore...'. The 'Disable Provisioning' button is highlighted. A confirmation window will appear, press OK to disable Provisioning. A screenshot of a confirmation dialog box. It contains the text 'Disable provisioning. Are you sure?' and two buttons: 'OK' and 'Cancel'. The message “<i>Warning Code 002</i>” may appear.
---	--	---

9. **Active NOAMP:**
Verify the
Archive Contents
and Database
Compatibility

Select the **Active NOAMP** server and click on the **Compare**.



The following screen is displayed; click the button for the restored database file that was uploaded as a part of **Step 13** of this procedure.



Verify that the output window matches the screen below.

Note: You will get a database mismatch regarding the NodeIDs of the VMs. That is expected. If that is the only mismatch, proceed, otherwise stop and contact My Oracle Support (MOS).



Note: Archive Contents and Database Compatibilities must be the following:

Archive Contents: Configuration data

Database Compatibility: The databases are compatible.

Note: The following is expected Output for Topology Compatibility Check since we are restoring from existing backed up data base to database with just one NOAMP:

Topology Compatibility
THE TOPOLOGY SHOULD BE COMPATIBLE MINUS THE NODEID.

Note: We are trying to restore a backed up database onto an empty NOAMP database. This is an expected text in Topology Compatibility.

If the verification is successful, Click **BACK** button and continue to **next step** in this procedure.


Procedure 1: Recovery Scenario 1 -- Complete Server Outage

10. ☐	Active NOAMP: Restore the Database	Click on Main Menu → Status & Manage → Database Select the Active NOAMP server, and click on Restore as shown below. The following screen will be displayed. Select the proper back up provisioning and configuration file. Database Restore Select archive to Restore on server: blade02 <table><tr><td>Archive</td><td> ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20100928_021502.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20100929_021501.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20100930_021501.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20101001_021501.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20101002_021502.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20101003_021502.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20101004_021502.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20101005_021501.AUTO.tar * </td><td>Select the archive to restore on blade02.</td></tr></table> OK Cancel Click OK Button. The following confirmation screen will be displayed. Note: You will get a database mismatch regarding the NodeIDs of the servers. That is expected. If that is the only mismatch, proceed, otherwise stop and contact My Oracle Support (MOS). Select the Force checkbox as shown above and Click OK to proceed with the DB restore. Database Restore Confirm Incompatible database selected Discrepancies: - IMI Server Address A3118.120 has different node IDs in current topology and the selected backup file. - Current node ID: A3118.120, Selected backup file node ID: B2073.087 - IMI Server Address C1157.241 has different node IDs in current topology and the selected backup file. - Current node ID: C1157.241, Selected backup file node ID: B2073.087 - IMI Server Address B1787.161 has different node IDs in current topology and the selected backup file. - Current node ID: B1787.161, Selected backup file node ID: B2073.087 Confirm archive "3bladeNPQR.blade07.Configuration.NETWORK_OAMP.20110119_184253.MAN.tar" to Restore on server: blade07 Force Restore? ☒ Force OK Cancel Force restore on blade07, despite compare errors. Note: After the restore has started, the user will be logged out of XMI NO GUI since the restored Topology is old data.	Archive	☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20100928_021502.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20100929_021501.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20100930_021501.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20101001_021501.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20101002_021502.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20101003_021502.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20101004_021502.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20101005_021501.AUTO.tar *	Select the archive to restore on blade02.
Archive	☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20100928_021502.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20100929_021501.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20100930_021501.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20101001_021501.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20101002_021502.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20101003_021502.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20101004_021502.AUTO.tar ☐ Backup.npq: blade02.Configuration.NETWORK_OAMP.20101005_021501.AUTO.tar *	Select the archive to restore on blade02.			


Procedure 1: Recovery Scenario 1 -- Complete Server Outage

11. ☐	Active NOAMP: Login	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of: http://<Primary_NOAMP_VIP_IP_Address> Login as the guiadmin user: 
12. ☐	Active NOAMP: Monitor and Confirm database restoral	Wait for 5-10 minutes for the System to stabilize with the new topology: Monitor the Info tab for “Success”. This will indicate that the backup is complete and the system is stabilized. Following alarms must be ignored for NOAMP and MP Servers until all the Servers are configured: Alarms with Type Column as “REPL” , “COLL”, “HA” (with mate NOAMP), “DB” (about Provisioning Manually Disabled) Note: Do not pay attention to alarms until all the servers in the system are completely restored. Note: The Configuration and Maintenance information will be in the same state it was backed up during initial backup.
13. ☐	Active NOAMP: Login	Login to the recovered Active NOAMP via SSH terminal as admusr user.


Procedure 1: Recovery Scenario 1 -- Complete Server Outage

14. ☐	Active NOAMP: Restore /etc/hosts/ File of the Active NOAMP	Execute the following command: \$ sudo AppWorks AppWorks_AppWorks updateServerAliases <NOAMP Host Name>
15. ☐	Active NOAMP: Recover Standby NOAMP (HA Deployments Only)	Configure the second NOAMP server by executing procedures from reference <i>Oracle Communications User Data Repository 12.11 Cloud Installation and Configuration Guide, latest revision [2]</i> : Procedure 4 “Create Configuration for Remaining Servers”, Step 22. Procedure 10 “Apply Configuration for Remaining Servers” for second NOAMP. Note: If Topology or nodeId alarms are persistent after the database restore, refer to the steps below.
16. ☐	Active NOAMP: Restart UDR application on Recovered NOAMP	Navigate to Main Menu → Status & Manage → Server ,  Select the recovered standby NOAMP server and click on Restart . Stop Restart Reboot NTP Sync Report

Procedure 1: Recovery Scenario 1 -- Complete Server Outage

17. ☐	Active NOAMP: Set HA on Standby NOAMP	Navigate to Status & Manage → HA  Click on Edit at the bottom of the screen Select the standby NOAMP server, set it to Active Press OK
18. ☐	Active NOAMP: Stop Replication to the C-Level Servers of this Site.	Inhibit Replication to the working C Level (MP) Servers which belong to the same site as of the failed SOAM servers, as the recovery of Active SOAM will cause the database wipeout in the C level servers because of the replication Execute Appendix B: Inhibit A and B Level Replication on C-Level Servers
19. ☐	Active NOAMP: Recover SOAM Server	Recover the SOAM server by executing procedures from reference <i>Oracle Communications User Data Repository 12.11 Cloud Installation and Configuration Guide, latest revision</i> [2]: Procedure 4 “Create Configuration for Remaining Servers”, Step 22. Procedure 10 “Apply Configuration for Remaining Servers” for SOAM

Procedure 1: Recovery Scenario 1 -- Complete Server Outage

20.	Active NOAMP: Restart UDR application on Recovered SOAM Server	Navigate to Main Menu → Status & Manage → Server,  Select the recovered server and click on Restart. Stop Restart Reboot NTP Sync Report
-----------------	---	--

Procedure 1: Recovery Scenario 1 -- Complete Server Outage

21. ☐	Active NOAMP: Upload the backed up SOAM Database file	Navigate to Main Menu → Status & Manage → Files Select the Active SOAM server. The following screen will appear. Click on Upload as shown below and select the file “<i>SO Provisioning and Configuration:</i>” file backed up after initial installation and provisioning. Click on Browse and Locate the backup file and click on Open as shown below. Click on the Upload button. The file will take a few seconds to upload depending on the size of the backup data. The file will be visible on the list of entries after the upload is complete.
--	---	---

Procedure 1: Recovery Scenario 1 -- Complete Server Outage


22. ☐	Recovered SOAM: Login	Establish a GUI session on the recovered SOAM server. Open the web browser and enter a URL of: http://<Recovered_SOAM_IP_Address> Login as the <i>guiadmin</i> user: ORACLE® Oracle System Login Log In Enter your username and password to log in Username: guiadmin Password: •••••••• ☐ Change password Log In Welcome to the Oracle System Login Unauthorized access is prohibited. This Oracle system requires the use of Microsoft Internet Explorer 8.0, 9.0, or 10.0 with support for JavaScript and cookies. Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.
--	----------------------------------	---

23.


Recovered SOAM: Verify the Archive Contents and Database Compatibility

Navigate to **Main Menu** → **Status & Manage** → **Database**

Select the **Active SOAM** server and click on the **Compare**.




The following screen is displayed; click the button for the restored database file that was uploaded as a part of **Step 13** of this procedure.



Verify that the output window matches the screen below.

Note: You will get a database mismatch regarding the NodeIDs of the VMs. That is expected. If that is the only mismatch, proceed, otherwise stop and contact My Oracle Support (MOS).



Note: Archive Contents and Database Compatibilities must be the following:

Archive Contents: Configuration data

Database Compatibility: The databases are compatible.

Note: The following is expected Output for Topology Compatibility Check since we are restoring from existing backed up data base to database with just one SOAM:

Topology Compatibility
THE TOPOLOGY SHOULD BE COMPATIBLE MINUS THE NODEID.

Note: We are trying to restore a backed up database onto an empty SOAM database. This is an expected text in Topology Compatibility.

If the verification is successful, Click **BACK** button and continue to **next step** in this procedure.



Procedure 1: Recovery Scenario 1 -- Complete Server Outage

24.	Recovered SOAM: Restore the Database	Click on Main Menu → Status & Manage → Database Select the Active SOAM server, and click on Restore as shown below. The following screen will be displayed. Select the proper back up provisioning and configuration file. Database Restore Select archive to Restore on server: blade02 Archive ☐ Backup.npq:blade02.Configuration.NETWORK_OAMP.20100928_021502.AUTO.tar ☐ Backup.npq:blade02.Configuration.NETWORK_OAMP.20100929_021501.AUTO.tar ☐ Backup.npq:blade02.Configuration.NETWORK_OAMP.20100930_021501.AUTO.tar ☐ Backup.npq:blade02.Configuration.NETWORK_OAMP.20101001_021501.AUTO.tar ☐ Backup.npq:blade02.Configuration.NETWORK_OAMP.20101002_021502.AUTO.tar ☐ Backup.npq:blade02.Configuration.NETWORK_OAMP.20101003_021502.AUTO.tar ☐ Backup.npq:blade02.Configuration.NETWORK_OAMP.20101004_021502.AUTO.tar ☐ Backup.npq:blade02.Configuration.NETWORK_OAMP.20101005_021501.AUTO.tar* Select the archive to restore on blade02. Ok Cancel Click OK Button. The following confirmation screen will be displayed. If you get an error that the NodeIDs do not match. That is expected. If no other errors beside the NodeIDs are displayed, select the Force checkbox as shown below and Click OK to proceed with the DB restore. Database Restore Confirm Incompatible database selected Discrepancies: - IMI Server Address A3118.120 has different node IDs in current topology and the selected backup file. Current node ID: A3118.120, Selected backup file node ID: B2073.087 - IMI Server Address C1157.241 has different node IDs in current topology and the selected backup file. Current node ID: C1157.241, Selected backup file node ID: B2073.087 - IMI Server Address B1787.161 has different node IDs in current topology and the selected backup file. Current node ID: B1787.161, Selected backup file node ID: B2073.087 Confirm archive "3bladeNPQR.blade07.Configuration.NETWORK_OAMP.20110119_184253.MAN.tar" to Restore on server: blade07 Force Restore? ☒ Force Force restore on blade07, despite compare errors. Ok Cancel Note: After the restore has started, the user will be logged out of XMI SOAM GUI since the restored Topology is old data.
----------------------------	---	--



Procedure 1: Recovery Scenario 1 -- Complete Server Outage

25. ☐	Recovered SOAM: Monitor and Confirm database restoral	Wait for 5-10 minutes for the System to stabilize with the new topology: Monitor the Info tab for “Success”. This will indicate that the backup is complete and the system is stabilized. Note: Do not pay attention to alarms until all the servers in the system are completely restored. Note: The Configuration and Maintenance information will be in the same state it was backed up during initial backup.
26. ☐	Active NOAMP: Login	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of: http://<Primary_NOAMP_VIP_IP_Address> Login as the guiadmin user: 



Procedure 1: Recovery Scenario 1 -- Complete Server Outage

27. ☐	Active NOAMP: Recover remaining SOAM (HA Deployments Only)	NOTE: For Non-HA sites SKIP this step. Recover second SOAM server by executing procedures from reference <i>Oracle Communications User Data Repository 12.11 Cloud Installation and Configuration Guide, latest revision</i> [2]: Procedure 4 “Create Configuration for Remaining Servers”, Step 22. Procedure 10 “Apply Configuration for Remaining Servers” for remaining SOAM. NOTE: Wait for server to reboot before continuing.
28.	Active NOAMP: Restart UDR application on remaining SOAM (HA Deployments Only)	NOTE: For Non-HA sites SKIP this step. Navigate to Main Menu → Status & Manage → Server,  Select the recovered server and click on Restart. 

Procedure 1: Recovery Scenario 1 -- Complete Server Outage


29. ☐	Active NOAMP: Set HA on Recovered SOAM (HA Deployments Only)	NOTE: For Non-HA sites SKIP this step. Navigate to Status & Manage → HA  Click on Edit at the bottom of the screen Set Max Allowed HA Role to Active Press OK
30. ☐	Active NOAMP: Start Replication on MP Servers	Un-Inhibit (<i>Start</i>) Replication to the MP Servers which belong to the <u>same site as of the failed SOAM</u> servers. Execute Appendix C Un-Inhibit A and B Level Replication on C-Level Servers Navigate to Main Menu → Status & Manage → Database If the “<i>Repl Status</i>” is set to “Inhibited”, click on the Allow Replication button as shown below using the following order, otherwise if none of the servers are inhibited, skip this step and continue with the next step: • Active NOAMP Server • Standby NOAMP Server • Active SOAM Server • Standby SOAM Server • MP Servers Verify that the replication on all the working servers is allowed. This can be done by clicking on each server and checking that the button below shows “Inhibit Replication”, and NOT “Allow Replication”. 

Procedure 1: Recovery Scenario 1 -- Complete Server Outage

31. ☐	Active NOAMP: Restart UDR application for Recovered MP	Navigate to Main Menu → Status & Manage → Server,  Select the recovered server and click on Restart. Stop Restart Reboot NTP Sync Report
32. ☐	Active NOAMP: Set HA on all MP Servers	Navigate to Status & Manage → HA  Click on Edit at the bottom of the screen For each server whose Max Allowed HA Role is set to Standby, set it to Active Press OK
33. ☐	Active NOAMP: Perform key exchange between the active-NOAMP and recovered servers.	Establish an SSH session to the Active NOAMP, login as admusr. Execute the following command to perform a keyexchange from the active NOAMP to each recovered server: <pre>\$ keyexchange admusr@<Recovered Server Hostname></pre>

34. **Active NOAMP:**
Fetch and Store
the database
Report for the
Newly Restored
Data and Save it

Navigate to **Main Menu → Status & Manage → Database**



Select the **active NOAMP** server and click on the **Report** button at the bottom of the page. The following screen is displayed:

Main Menu: Status & Manage -> Database [Report] Help Tue Oct 05 15:13:38 2010 UTC

=====

N F Q R Database Status Report

=====

Report Generated: Tue Oct 05 15:13:38 2010 UTC

From: Active Network OAM&P on host blade07

Report Version: 3.0.13-3.0.0_10.13.0

User: guidadmin

General

Hostname : blade07

Appworks Database Version : 3.0

Application Database Version :

Capacities and Utilization

Disk Utilization 0.6%: 249M used of 40G total, 38G available

Memory Utilization 0.6%: 136M used of 23975M total, 23839M available

Alarms

None

Maintenance in Progress

Restore operation success

Service Information

Part: A_NpqrProvPart

Table Name	Schema	Row Size Avg Max	Num Rows	Memory Used / Alloc	Disk Used / Alloc
CgPa		44	1	44 B	44 B
CgPaGta		52	0	0 B	0 B
CgPaInfo		64	1	64 B	64 B
CgPaOpc		36	0	0 B	0 B
CountryCode		24	306	7344 B	7344 B
GTCConfig		52	2	104 B	104 B
MccMnc		40	0	0 B	0 B
Msisdn		52	0	0 B	0 B
Msrn		68	0	0 B	0 B
NpqrNeOptions		276	0	0 B	0 B

=====

Print Save


Click on **Save** and save the report to your local machine.

37.

Active NOAMP:

Verify the HA Status

Click on Main Menu → Status and Manage → HA



Select the row for all of the servers

Verify that the “HA Role” is either “Active” or “Standby”.


Hostname	OAM Max HA Role	Application Max HA Role	Max Allowed HA Role	Mate Hostname List	Network Element	Server Role	Active VIPs
NO2	Active	OOS	Active	NO1	NO_10303	Network OAM&P	10.240.70.132
SO1	Standby	OOS	Active	SO2	SO_10303	System OAM	
SO2	Active	OOS	Active	SO1	SO_10303	System OAM	10.240.70.133
MP1	Standby	Active	Active	MP2	SO_10303	MP	
MP2	Active	Active	Active	MP1	SO_10303	MP	
IPFE	Active	OOS	Active		SO_10303	MP	

38.

Active NOAMP:

Enable Provisioning

Click on Main Menu → Status & Manage → Database



Enable Provisioning by clicking on **Enable Provisioning** button at the bottom of the screen as shown below.

Enable Provisioning

Report

Inhibit/Allow Replication

Backup...

Compare...

Restore...

Man Audit



Suspend Auto Audit



A confirmation window will appear, press **OK** to enable Provisioning.




Enable provisioning.
Are you sure?

OK

Cancel

39. ☐	Active SOAM: Verify the Local Node Info	Navigate to Main Menu → Diameter → Configuration → Local Node  Verify that all the local nodes are shown.
40. ☐	Active SOAM: Verify the Peer Node Info	Navigate to Main Menu → Diameter → Configuration → Peer Node  Verify that all the peer nodes are shown.

41. ☐	Active SOAM: Verify the Connections Info	Navigate to Main Menu → Diameter → Configuration → Connections  Verify that all the connections are shown.
42. ☐	Active SOAM: Enable Connections if needed	Navigate to Main Menu → Diameter → Maintenance → Connections  Select each connection and click on the Enable button. Alternatively you can enable all the connections by selecting the EnableAll button. Enable Disable EnableAll DisableAll Diagnose Start Diagnose End SCTP STATISTICS ☐ Pause updates Verify that the Operational State is Available.

43. ☐	Active SOAM: Enable SPR Features	Navigate to Main Menu → Diameter → Maintenance → Applications  Select the feature application. Click the Enable button. Enable Disable ☐ Pause updates
44. ☐	Active SOAM: Examine All Alarms	Navigate to Main Menu → Alarms & Events → View Active  Examine all active alarms and refer to the on-line help on how to address them. If needed contact My Oracle Support (MOS).
45. ☐	Active NOAMP: Examine All Alarms	Login to the NOAMP VIP if not already logged in. Navigate to Main Menu → Alarms & Events → View Active  Examine all active alarms and refer to the on-line help on how to address them. If needed contact My Oracle Support (MOS).
46. ☐	Restore GUI Username and Passwords	If applicable, Execute steps in Section 5 to recover the user and group information restored.
47. ☐	Backup and Archive All the Databases from the Recovered System	Execute Appendix A Oracle Communications User Data Repository Database Backup to back up the Configuration databases.
THIS PROCEDURE HAS BEEN COMPLETED		

4.1.2 Recovery Scenario 2 (Partial Server Outage with one NOAMP server intact and both SOAMs failed)

For a partial server outage with an NOAMP server intact and available; SOAM servers are recovered using recovery procedures for software and then executing a database restore to the active SOAM server using a database backup file obtained from the SOAM servers. All other servers are recovered using recovery procedures for software. Database replication from the active NOAMP server will recover the database on these servers. The major activities are summarized in the list below. Use this list to understand the recovery procedure summary. Do not use this list to execute the procedure. The actual procedures' detailed steps are in **Procedure 2**. The major activities are summarized as follows:

Recover **Standby NOAMP** server (*if needed*) by recovering software and the database.

- Recover the software.

Recover **Active SOAM** server by recovering software.

- Recover the software.
- Recover the Database.



Recover any failed **SOAM and MP** servers by recovering software.

- Recover the software.
- The database has already been restored at the active SOAM server and does not require restoration at the SO and MP servers.




Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

S T E P #	This procedure performs recovery if at least 1 NOAMP server is available but all SOAM servers in a site have failed. This includes any SOAM server that is in another location. Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number. If this procedure fails, contact My Oracle Support (MOS), and ask for assistance.
1. ☐	Gather Required Materials Gather the documents and required materials listed in Section Required Materials
2. ☐	Active NOAMP: Login Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of: http://<Primary_NOAMP_VIP_IP_Address> Login as the <i>guiadmin</i> user: 


Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

3. ☐	Active NOAMP: Set Failed Servers to Standby	Navigate to Main Menu → Status & Manage → HA  Select Edit Set the Max Allowed HA Role drop down box to Standby for the failed servers. Select Ok 
4. ☐	Create VMs Recover the Failed Software	Execute the following procedures from reference <i>Oracle Communications User Data Repository 12.11 Cloud Installation and Configuration Guide, latest revision</i> [2]: Procedure 2 : Deploy Oracle Communications User Data Repository Virtual Machines on VMware
5. ☐	Repeat for Remaining Failed Servers	If necessary, repeat step 5 for all remaining failed servers.
6. ☐	Active NOAMP: Login	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of: http://<Primary_NOAMP_VIP_IP_Address> Login as the guiadmin user: 


Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

7. ☐	Active NOAMP: Recover Standby NOAMP	Configure the standby NOAMP server by executing procedures from reference <i>Oracle Communications User Data Repository 12.11 Cloud Installation and Configuration Guide, latest revision</i> [2]: Procedure 4 “Create Configuration for Remaining Servers”, Step 22. Procedure 10 “Apply Configuration for Remaining Servers” for NOAMP. Note: If Topology or nodeId alarms are persistent after the database restore, refer to the steps below.
8. ☐	Active NOAMP: Restart UDR application on Recovered NOAMP	Navigate to Main Menu → Status & Manage → Server,  Select the recovered standby NOAMP server and click on Restart. 
9. ☐	Active NOAMP: Set HA on Recovered NOAMP	Navigate to Status & Manage → HA  Click on Edit at the bottom of the screen Select the standby NOAMP server, set it to Active Press OK




Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

10. ☐	Active NOAMP: Stop Replication to the MP Servers of this Site.	Inhibit Replication to the working C Level Servers which belong to the same site as the failed SOAM servers, as the recovery of Active SOAM will cause the database wipeout in the C level servers because of the replication Execute Appendix B Inhibit A and B Level Replication on C-Level Servers
11. ☐	Active NOAMP: Recover SOAM Server	Recovery the SOAM server by executing procedures from reference <i>Oracle Communications User Data Repository 12.11 Cloud Installation and Configuration Guide, latest revision</i> [2]: Procedure 4 “Create Configuration for Remaining Servers”, Step 22. Procedure 10 “Apply Configuration for Remaining Servers” for SOAM
12. ☐	Active NOAMP: Restart UDR application on Recovered SOAM	Navigate to Main Menu → Status & Manage → Server  Select the recovered SOAM server and click on Restart. Stop Restart Reboot NTP Sync Report

Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

13.	Active NOAMP: Set HA on Recovered SOAM	Navigate to Status & Manage → HA  Click on Edit at the bottom of the screen Select the SOAM server, set it to Active Press OK
-----	---	--

Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

14. Active NOAMP: Upload the backed up SOAM Database file	Navigate to Main Menu → Status & Manage → Files Select the Active SOAM server. The following screen will appear. Click on Upload as shown below and select the file “<i>SO Provisioning and Configuration:</i>” file backed up after initial installation and provisioning.  Click on Browse and Locate the backup file and click on Open as shown below.   Click on the Upload button. The file will take a few seconds to upload depending on the size of the backup data. The file will be visible on the list of entries after the upload is complete.
--	--

Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

15. ☐	Recovered SOAM: Login	Establish a GUI session on the recovered SOAM server. Open the web browser and enter a URL of: <code>http://<Recovered_SOAM_IP_Address></code> Login as the <i>guiadmin</i> user: 
---------------------------------	------------------------------	--

16. **Recovered SOAM: Verify the Archive Contents and Database Compatibility**

Navigate to **Main Menu → Status & Manage → Database**

Select the **Active SOAM** server and click on the **Compare**.

The following screen is displayed; click the button for the restored database file that was uploaded as a part of this procedure.

Database Compare

Select archive to compare on server: blade02

Archive

- ☒ Backup.nprq blade02.Configuration.NETWORK_OAMP.20100928_021502.AUTO.tar
- ☐ Backup.nprq blade02.Configuration.NETWORK_OAMP.20100929_021501.AUTO.tar
- ☐ Backup.nprq blade02.Configuration.NETWORK_OAMP.20100930_021501.AUTO.tar
- ☐ Backup.nprq blade02.Configuration.NETWORK_OAMP.20101001_021501.AUTO.tar
- ☐ Backup.nprq blade02.Configuration.NETWORK_OAMP.20101002_021502.AUTO.tar
- ☐ Backup.nprq blade02.Configuration.NETWORK_OAMP.20101003_021502.AUTO.tar
- ☐ Backup.nprq blade02.Configuration.NETWORK_OAMP.20101004_021502.AUTO.tar
- ☐ Backup.nprq blade02.Configuration.NETWORK_OAMP.20101005_021501.AUTO.tar *

Select the archive to compare to the current database.

Verify that the output window matches the screen below.

Note: You will get a database mismatch regarding the NodeIDs of the VMs. That is expected. If that is the only mismatch, proceed, otherwise stop and contact My Oracle Support (MOS)

```
The selected database came from blade07 on 01/10/2011 at 13:43:47 EDT and contains the following comment:
*
*
* Archive Contents
* Provisioning/Configuration data
*
* Database Compatibility
* The databases are compatible.
*
* Node Type Compatibility
* The node types are compatible.
*
* Topology Compatibility
* THE TOPOLOGY IS NOT COMPATIBLE. CONTACT TERELEC CUSTOMER SERVICES BEFORE RESTORING THIS DATABASE.

Discrepancies
- INI Server Address A2118.120 has different code ID in current topology and the selected backup file.
  Current node ID: A2118.120. Selected backup file node ID: B2073.087
- INI Server Address C1157.241 has different code ID in current topology and the selected backup file.
  Current node ID: C1157.241. Selected backup file node ID: B2073.087
- INI Server Address B1787.161 has different code ID in current topology and the selected backup file.
  Current node ID: B1787.161. Selected backup file node ID: B2073.087

*
* User Compatibility
* The user and authentication data are compatible.
*
* Contents
* Provisioning/Configuration
*
* Table Instance Counts
* Current ASGroup count: 0 Selected: 0
* Current AdjacentServers count: 0 Selected: 0
* Current AppworksCapacityConstraints count: 2 Selected: 2
* Current Association count: 0 Selected: 0
* Current AssociationCFOSet count: 1 Selected: 1
* Current AuthKeys count: 2 Selected: 6
* Current Authentication count: 1 Selected: 1
```

Note: Archive Contents and Database Compatibilities must be the following:

Archive Contents: Configuration data

Database Compatibility: The databases are compatible.

Note: The following is expected Output for Topology Compatibility Check since we are restoring from existing backed up data base to database with just one SOAM:

Topology Compatibility

THE TOPOLOGY SHOULD BE COMPATIBLE MINUS THE NODEID.


Note: We are trying to restore a backed up database onto an empty SOAM database. This is an expected text in Topology Compatibility.

If the verification is successful, Click **BACK** button and continue to **next step** in this procedure.


Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

17. Recovered SOAM: Restore the Database	Click on Main Menu → Status & Manage → Database Select the Active SOAM server, and click on Restore as shown below. The following screen will be displayed. Select the proper back up provisioning and configuration file. Database Restore Select archive to Restore on server: blade02 Archive ☐ Backup.npqr.blade02.Configuration.NETWORK_OAMP.20100928_021502.AUTO.tar ☐ Backup.npqr.blade02.Configuration.NETWORK_OAMP.20100929_021501.AUTO.tar ☐ Backup.npqr.blade02.Configuration.NETWORK_OAMP.20100930_021501.AUTO.tar ☐ Backup.npqr.blade02.Configuration.NETWORK_OAMP.20101001_021501.AUTO.tar ☐ Backup.npqr.blade02.Configuration.NETWORK_OAMP.20101002_021502.AUTO.tar ☐ Backup.npqr.blade02.Configuration.NETWORK_OAMP.20101003_021502.AUTO.tar ☐ Backup.npqr.blade02.Configuration.NETWORK_OAMP.20101004_021502.AUTO.tar ☐ Backup.npqr.blade02.Configuration.NETWORK_OAMP.20101005_021501.AUTO.tar* Select the archive to restore on blade02. Ok Cancel Click OK Button. The following confirmation screen will be displayed. Note: You will get a database mismatch regarding the NodeIDs of the servers. That is expected. If that is the only mismatch, proceed, otherwise stop and contact My Oracle Support (MOS). Select the Force checkbox as shown above and Click OK to proceed with the DB restore. Database Restore Confirm Incompatible database selected Discrepancies: - IMI Server Address A3118.120 has different node IDs in current topology and the selected backup file. Current node ID: A3118.120, Selected backup file node ID: B2073.087 - IMI Server Address C1157.241 has different node IDs in current topology and the selected backup file. Current node ID: C1157.241, Selected backup file node ID: B2073.087 - IMI Server Address B1787.161 has different node IDs in current topology and the selected backup file. Current node ID: B1787.161, Selected backup file node ID: B2073.087 Confirm archive "3bladeNPQR.blade07.Configuration.NETWORK_OAMP.20110119_184253.MAN.tar" to Restore on server: blade07 Force Restore? ☒ Force Force restore on blade07, despite compare errors. Ok Cancel Note: After the restore has started, the user will be logged out of XMI SOAM GUI since the restored Topology is old data.
---	--

Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

18. ☐	Recovered SOAM: Monitor and Confirm database restoral	Wait for 5-10 minutes for the System to stabilize with the new topology: Monitor the Info tab for “Success”. This will indicate that the backup is complete and the system is stabilized. Note: Do not pay attention to alarms until all the servers in the system are completely restored. Note: The Configuration and Maintenance information will be in the same state it was backed up during initial backup.
19. ☐	Active NOAMP: Recover remaining SOAM Server (HA Deployments Only)	NOTE: For Non-HA sites SKIP this step Configure the remaining SOAM server by executing procedures from reference <i>Oracle Communications User Data Repository 12.11 Cloud Installation and Configuration Guide, latest revision</i> [2]: Procedure 4 “Create Configuration for Remaining Servers”, Step 22. Procedure 10 “Apply Configuration for Remaining Servers” for second SOAM. NOTE: Wait for server to reboot before continuing.
20. ☐	Active NOAMP: Restart UDR application on Recovered SOAM (HA Deployments Only)	Navigate to Main Menu → Status & Manage → Server  Select the recovered SOAM server and click on Restart. Stop Restart Reboot NTP Sync Report




Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

21. ☐	Active NOAMP: Set HA on SOAM Servers (HA Deployments Only)	NOTE: For Non-HA sites SKIP this step Navigate to Status & Manage → HA  Click on Edit at the bottom of the screen For each SOAM server whose Max Allowed HA Role is set to Standby, set it to Active Press OK
22. ☐	Recovered Servers: Login	Establish an SSH to the recovered server’s XMI address:



Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

23.	Recovered Servers: Sync NTP	1) Perform the following to retrieve the remote NTP server: <pre>\$ sudo ntpq -np</pre> Example output: <pre>[admusr@NOAMP-2 ~]\$ ntpq -np</pre><table><tr><th>remote jitter</th><th>refid</th><th>st</th><th>t</th><th>when</th><th>poll</th><th>reach</th><th>delay</th><th>offset</th></tr><tr><td colspan="9">=====</td></tr><tr><td>*10.240.9.186 2.434</td><td>10.250.33.2</td><td>3</td><td>u</td><td>356</td><td>1024</td><td>377</td><td>1.409</td><td>0.113</td></tr></table> 2) Stop ntpd service: <pre>\$ sudo service ntpd stop</pre> 3) Sync the date to the ntp remote server: <pre>\$ sudo ntpdate <NTP remote server></pre> Note: The remote server below will be that of the one gathered in sub step 1. 4) Start the ntp service: <pre>\$ sudo service ntpd start</pre>	remote jitter	refid	st	t	when	poll	reach	delay	offset	=====									*10.240.9.186 2.434	10.250.33.2	3	u	356	1024	377	1.409	0.113
remote jitter	refid	st	t	when	poll	reach	delay	offset																					
=====																													
*10.240.9.186 2.434	10.250.33.2	3	u	356	1024	377	1.409	0.113																					


Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

24. ☐	Active NOAMP: Restart UDR application on Recovered servers (HA Deployments Only)	NOTE: For Non-HA sites SKIP this step Navigate to Main Menu → Status & Manage → Server,  Select the recovered server and click on Restart. 
25. ☐	Active NOAMP: Start Replication on MP Servers	Un-Inhibit (<i>Start</i>) Replication to the MP Servers which belong to the <u>same site as of the failed SOAM</u> servers. Execute Appendix C Un-Inhibit A and B Level Replication on C-Level Servers Navigate to Main Menu → Status & Manage → Database If the “<i>Repl Status</i>” is set to “Inhibited”, click on the Allow Replication button as shown below using the following order, otherwise if none of the servers are inhibited, skip this step and continue with the next step: • Active NOAMP Server • Standby NOAMP Server • Active SOAM Server • Standby SOAM Server • MP Servers Verify that the replication on all the working servers is allowed. This can be done by clicking on each server and checking that the button below shows “Inhibit Replication”, and NOT “Allow Replication”. 

Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

26. ☐	Active NOAMP: Start replication on ALL Servers	Un-Inhibit (<i>Start</i>) Replication to the ALL C-Level (MP) Servers Navigate to Status & Manage → Database A screenshot of a software interface showing a tree view under the heading 'Status & Manage'. The tree includes items: Network Elements, Server, HA, Database (highlighted with a blue selection bar), KPIs, Processes, Tasks, and Files. If the “<i>Repl Status</i>” is set to “Inhibited”, click on the Allow Replication button as shown below using the following order: • Active NOAMPP Server • Standby NOAMPP Server • Active SOAM Server • Standby SOAM Server • MP Servers Verify that the replication on all servers is allowed. This can be done by clicking on each server and checking that the button below shows “Inhibit Replication”, and NOT “Allow Replication”. A screenshot of a toolbar containing several buttons: 'Disable Provisioning', 'Report...', 'Allow Replication' (circled in red), 'Backup...', 'Compare...', and 'Restore...'. There is also a small icon of three diamonds to the right of the buttons.
--	--	--

Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact


27. ☐	Active NOAMP: Set HA on all MP Servers	Navigate to Status & Manage → HA  Click on Edit at the bottom of the screen For each server whose Max Allowed HA Role is set to Standby, set it to Active Press OK
28. ☐	Active NOAMP: Perform key exchange between the active-NOAMP and recovered servers.	Establish an SSH session to the Active NOAMP, login as <i>admusr</i>. Execute the following command to perform a keyexchange from the active NOAMP to each recovered server: <pre>\$ keyexchange admusr@<Recovered Server Hostname></pre> Note: If an export server is configured, perform this step.

Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

29.

Active NOAMP:
Fetch and Store the
database Report for
the Newly
Restored Data and
Save it

Navigate to **Main Menu → Status & Manage → Database**



Select the **active** NOAMP server and click on the **Report** button at the bottom of the page. The following screen is displayed:

Main Menu: Status & Manage -> Database [Report]

Report Generated: Tue Oct 05 15:13:38 2010 UTC
From: Active Network OAM&P on host blade07
Report Version: 3.0.13-3.0.0_10.13.0
User: guadmin

General

Hostname : blade07
Appworks Database Version : 3.0
Application Database Version :

Capacities and Utilization

Disk Utilization 0.6%: 249M used of 40G total, 38G available
Memory Utilization 0.6%: 136M used of 23975M total, 23839M available

Alarms

None

Maintenance in Progress

Restore operation success

Service Information

Part: A_NpqrProvPart

Table Name	Schema	Row Size		Num Rows	Memory		Disk	
		Avg	Max		Used	Alloc	Used	Alloc
CgPa		44		1	44 B	44 B	44 B	44 B
CgPaGta		52		0	0 B	0 B	0 B	0 B
CgPaInfo		64		1	64 B	64 B	64 B	64 B
CgPaOpc		36		0	0 B	0 B	0 B	0 B
CountryCode		24		306	7344 B	7344 B	7344 B	7344 B
GTConfig		52		2	104 B	104 B	104 B	104 B
MccMnc		40		0	0 B	0 B	0 B	0 B
Msisdn		52		0	0 B	0 B	0 B	0 B
Msrn		68		0	0 B	0 B	0 B	0 B
NpqrNeOptions		276		0	0 B	0 B	0 B	0 B

Print Save

Click on **Save** and save the report to your local machine.

Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact


30.	Active NOAMP: ☐ Verify Replication Between Servers.	Login to the Active NOAMP via SSH terminal as <i>admusr</i> user. Execute the following command: \$ sudo irepstat -m Output like below shall be generated: -- Policy 0 ActStb [DbReplication] ----- ----- RDU06-MP1 -- Stby BC From RDU06-S01 Active00.50 ^0.17%cpu 42B/s A=none CC From RDU06-MP2 Active00.10 ^0.17 0.88%cpu 32B/s A=none RDU06-MP2 -- Active BC From RDU06-S01 Active00.50 ^0.10%cpu 33B/s A=none CC To RDU06-MP1 Active00.10 0.08%cpu 20B/s A=none RDU06-N01 -- Active AB To RDU06-S01 Active00.50 1%R 0.03%cpu 21B/s RDU06-S01 -- Active AB From RDU06-N01 Active00.50 ^0.04%cpu 24B/s BC To RDU06-MP1 Active00.50 1%R 0.04%cpu 21B/s BC To RDU06-MP2 Active00.50 1%R 0.07%cpu 21B/s
-----	--	--

Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

31.

Active NOAMP:
Verify the Database states

Click on Main Menu → Status and Manager → Database




Verify that the “OAM Max HA Role” is either “Active” or “Standby” for NOAMP and SOAM and “Application Max HA Role” for MPs is “Active”, and that the status is “Normal” as shown below:

Network Element	Server	Role	OAM Max HA Role	Application Max HA Role	Status	DB Level	OAM Repl Status	SIG Repl Status	Repl Status	Repl Audit Status
NO_10303	NO2	Network OAM&P	Active	OOS	Normal	0	Normal	NotApplicabl	Allowed	AutoInProg
SO_10303	PSBR	MP	Active	Active	Normal	0	Normal	Normal	Allowed	AutoInProg
SO_10303	MP2	MP	Active	Active	Normal	0	Normal	Normal	Allowed	AutoInProg
SO_10303	SO1	System OAM	Standby	OOS	Normal	0	Normal	NotApplicabl	Allowed	AutoInProg
NO_10303	NO1	Network OAM&P	Standby	OOS	Normal	0	Normal	NotApplicabl	Allowed	AutoInProg
SO_10303	IPFE	MP	Active	OOS	Normal	0	Normal	Normal	Allowed	AutoInProg
SO_10303	SO2	System OAM	Active	OOS	Normal	0	Normal	NotApplicabl	Allowed	AutoInProg

32.

Active NOAMP:
Verify the HA Status

Click on Main Menu → Status and Manage → HA





Select the row for all of the servers



Verify that the “HA Role” is either “Active” or “Standby”.

Hostname	OAM Max HA Role	Application Max HA Role	Max Allowed HA Role	Mate Hostname List	Network Element	Server Role	Active VIPs
NO2	Active	OOS	Active	NO1	NO_10303	Network OAM&P	10.240.70.132
SO1	Standby	OOS	Active	SO2	SO_10303	System OAM	
SO2	Active	OOS	Active	SO1	SO_10303	System OAM	10.240.70.133
MP1	Standby	Active	Active	MP2	SO_10303	MP	
MP2	Active	Active	Active	MP1	SO_10303	MP	
IPFE	Active	OOS	Active		SO_10303	MP	




Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

33. ☐	Active SOAM: Verify the Local Node Info	Navigate to Main Menu → Diameter → Configuration → Local Node  Verify that all the local nodes are shown.
34. ☐	Active SOAM: Verify the Peer Node Info	Navigate to Main Menu → Diameter → Configuration → Peer Node  Verify that all the peer nodes are shown.

Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

35. ☐	Active SOAM: Verify the Connections Info	Navigate to Main Menu → Diameter → Configuration → Connections  Verify that all the connections are shown.
36. ☐	Active SOAM: Enable Connections if needed	Navigate to Main Menu → Diameter → Maintenance → Connections  Select each connection and click on the Enable button. Alternatively you can enable all the connections by selecting the EnableAll button. Enable Disable EnableAll DisableAll Diagnose Start Diagnose End SCTP STATISTICS ☐ Pause updates Verify that the Operational State is Available.

Procedure 2: Recovery Scenario 2 – Partial Outage One NOAMP Intact

37. ☐	Active SOAM: Enable SPR Features	Navigate to Main Menu → Diameter → Maintenance → Applications  Select the feature application Click the Enable button. Enable Disable ☐ Pause updates
38. ☐	Active SOAM: Examine All Alarms	Navigate to Main Menu → Alarms & Events → View Active  Examine all active alarms and refer to the on-line help on how to address them. If needed contact My Oracle Support (MOS).
39. ☐	Active NOAMP: Examine All Alarms	Login to the NOAMP VIP if not already logged in. Navigate to Main Menu → Alarms & Events → View Active  Examine all active alarms and refer to the on-line help on how to address them. If needed contact My Oracle Support (MOS).
40. ☐	Backup and Archive All the Databases from the Recovered System	Execute Appendix A Oracle Communications User Data Repository Database Backup to back up the Configuration database.
THIS PROCEDURE HAS BEEN COMPLETED		

4.1.3 Recovery Scenario 3 (Partial Server Outage with all NOAMP servers failed and one SOAM server intact)

For a partial server outage with an SOAM server intact and available; NOAMP servers are recovered using recovery procedures for software and then executing a database restore to the active NOAMP server using a NOAMP database backup file obtained from external backup sources such as customer servers. All other servers are recovered using recovery procedures for software. Database replication from the active NOAMP/active SOAM server will recover the database on these servers. The major activities are summarized in the list below. Use this list to understand the recovery procedure summary. Do not use this list to execute the procedure. The actual procedures' detailed steps are in **Procedure 3**. The major activities are summarized as follows:

Recover **Active NOAMP** server by recovering software and the database.

- Recover the software.
- Recover the database

Recover **Standby NOAMP servers** by recovering software.

- Recover the software.

Recover any failed **SOAM and MP servers** by recovering software.

- Recover the software.
- Database is already intact at one SOAM server and does not require restoration at the other SOAM and MP servers.

Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact


S T E P #	This procedure performs recovery if ALL NOAMP servers are failed but 1 or more SOAM servers are intact. Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number. If this procedure fails, contact My Oracle Support (MOS) , and ask for assistance.	
1. ☐	Gather Required Materials	Gather the documents and required materials listed in Section Required Materials
2. ☐	Recover the Failed Software	Execute the following procedures from reference <i>Oracle Communications User Data Repository 12.11 Cloud Installation and Configuration Guide, latest revision</i> [2]: Procedure 2 : Deploy Oracle Communications User Data Repository Virtual Machines on VMware
3. ☐	Obtain Latest Database Backup and Network Configuration Data.	Obtain the most recent database backup file from external backup sources (ex. file servers) or tape backup sources. From required materials list in Section Required Materials ; use site survey documents and Network Element report (if available), to determine network configuration data.
4. ☐	Execute UDR Installation Procedure for the First NOAMP	Configure the First NOAMP server by executing procedures from reference <i>Oracle Communications User Data Repository 12.11 Cloud Installation and Configuration Guide, latest revision</i> [2]: Procedure 3 “Configure NOAMP-A Server (1 st NOAMP Only)” for first NOAMP. Note: If Topology or nodeId alarms are persistent after the database restore, refer to the steps below.
5. ☐	Active NOAMP: Login	Login to the NOAMP GUI as the guiadmin user: Welcome to the Oracle System Login Unauthorized access is prohibited. This Oracle system requires the use of Microsoft Internet Explorer 8.0, 9.0, or 10.0 with support for JavaScript and cookies. Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

6.

Active NOAMP:
Upload the
Backed up
Database File

Browse to **Main Menu** → **Status & Manage** → **Files**



Select the Active NOAMP server. The following screen will appear:

Cpa1-NO	Cpa1-IPFE	Cpa1-Sbr1	Cpa1-Mp1	Cpa1-Mp2	Cpa1-Mp3	Cpa1-Sbr2
File Name	Size	Type	Timestamp			
Backup.dsr.Cpa1-NO.Configuration.NETWORK_OAMP.20120321_021501.AUTO.tar	720 KB	tar	2012-03-21 06:15:02 UTC			

Click on **Upload** as shown below and select the file “*NO Provisioning and Configuration:*” file backed up after initial installation and provisioning.

Delete

View

Upload

Download

0 used (0%) of 0 available | System utilization: 0 (0%) of 0 available.

Click on **Browse** and locate the backup file and click on Open as shown below.

File:

Browse...

Upload

Cancel

Choose file

Look in: PV3

Backup EAGLEVpelCOMProv.tgz

Backup PV3.tgz

PV3_NetHawk.txt

File name: Backup.PV3.tgz

Files of type: All Files (*.*)

Open

Cancel

Click on the **Upload** button.

The file will take a few seconds to upload depending on the size of the backup data. The file will be visible on the list of entries after the upload is complete.



Release 15.1

Confidential - Oracle Restricted \Employees Only

65

August 2026

Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

7. ☐	Active NOAMP: Disable Provisioning	Click on Main Menu → Status & Manage → Database A screenshot of a software interface showing a 'Status & Manage' menu. The menu is a vertical list of items: Network Elements, Server, Replication, Collection, HA, Database (highlighted with a dashed border), KPIs, Processes, and Files. Each item has a small icon to its left. Disable Provisioning by clicking on Disable Provisioning button at the bottom of the screen as shown below. A screenshot of a row of buttons: 'Disable Provisioning', 'Report...', 'Inhibit/Allow', 'Backup...', 'Compare...', and 'Restore...'. The 'Disable Provisioning' button is highlighted. A confirmation window will appear, press OK to disable Provisioning. A screenshot of a confirmation dialog box. It has a title bar and contains the text 'Disable provisioning. Are you sure?'. At the bottom are two buttons: 'OK' and 'Cancel'. The message “<i>Warning Code 002</i>” may appear.
---	--	--

Release 15.1 67 August 2026
Confidential - Oracle Restricted \Employees Only


Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

9. ☐	Active NOAMP: Restore the Database	Click on Main Menu → Status & Manage → Database Select the Active NOAMP server, and click on Restore as shown below. The following screen will be displayed. Select the proper back up provisioning and configuration file. Database Restore Select archive to Restore on server: blade02 Archive ☐ Backup.npqr.blade02.Configuration.NETWORK_OAMP.20100928_021502.AUTO.tar ☐ Backup.npqr.blade02.Configuration.NETWORK_OAMP.20100929_021501.AUTO.tar ☐ Backup.npqr.blade02.Configuration.NETWORK_OAMP.20100930_021501.AUTO.tar ☐ Backup.npqr.blade02.Configuration.NETWORK_OAMP.20101001_021501.AUTO.tar ☐ Backup.npqr.blade02.Configuration.NETWORK_OAMP.20101002_021502.AUTO.tar ☐ Backup.npqr.blade02.Configuration.NETWORK_OAMP.20101003_021502.AUTO.tar ☐ Backup.npqr.blade02.Configuration.NETWORK_OAMP.20101004_021502.AUTO.tar ☐ Backup.npqr.blade02.Configuration.NETWORK_OAMP.20101005_021501.AUTO.tar * Select the archive to restore on blade02. Ok Cancel Click OK Button. The following confirmation screen will be displayed. Note: You will get a database mismatch regarding the NodeIDs of the servers. That is expected. If that is the only mismatch, proceed, otherwise stop and contact My Oracle Support (MOS). Select the Force checkbox as shown above and Click OK to proceed with the DB restore. Database Restore Confirm Incompatible database selected Discrepancies: - IMI Server Address A3118.120 has different node IDs in current topology and the selected backup file. Current node ID: A3118.120, Selected backup file node ID: B2073.087 - IMI Server Address C1157.241 has different node IDs in current topology and the selected backup file. Current node ID: C1157.241, Selected backup file node ID: B2073.087 - IMI Server Address B1787.161 has different node IDs in current topology and the selected backup file. Current node ID: B1787.161, Selected backup file node ID: B2073.087 Confirm archive "3bladeNPQR.blade07.Configuration.NETWORK_OAMP.20110119_184253.MAN.tar" to Restore on server: blade07 Force Restore? ☒ Force Force restore on blade07, despite compare errors. Ok Cancel Note: After the restore has started, the user will be logged out of XMI NO GUI since the restored Topology is old data.
---	--	---


Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

10. ☐	Active NOAMP: Login	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of: http://<Primary_NOAMP_VIP_IP_Address> Login as the <i>guiadmin</i> user: 
11. ☐	Active NOAMP: Monitor and Confirm database restoral	Wait for 5-10 minutes for the System to stabilize with the new topology: Monitor the Info tab for “Success”. This will indicate that the backup is complete and the system is stabilized. Following alarms must be ignored for NOAMP and MP Servers until all the Servers are configured: Alarms with Type Column as “REPL”, “COLL”, “HA” (with mate NOAMP), “DB” (about Provisioning Manually Disabled) Note: Do not pay attention to alarms until all the servers in the system are completely restored. Note: The Configuration and Maintenance information will be in the same state it was backed up during initial backup.
12. ☐	Active NOAMP: Login	Login to the recovered Active NOAMP via SSH terminal as <i>admusr</i> user.

Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

13. ☐	Active NOAMP: Restore /etc/hosts/ File of the Active NOAMP	Execute the following command: <pre>\$ sudo AppWorks AppWorks_AppWorks updateServerAliases <NOAMP Host Name></pre>
14. ☐	Active NOAMP: Re-enable Provisioning	Navigate to Main Menu → Status & Manage → Database  Click on the Enable Provisioning . A pop-up window will appear to confirm as shown below, press OK . 
15. ☐	Active NOAMP: Recover Standby NOAMP (HA Deployments Only)	Configure the second NOAMP server by executing procedures from reference <i>Oracle Communications User Data Repository 12.11 Cloud Installation and Configuration Guide, latest revision</i> [2]: Procedure 4 “Create Configuration for Remaining Servers”, Step 2. Procedure 10 “Apply Configuration for Remaining Servers” for second NOAMP. Note: If Topology or nodeId alarms are persistent after the database restore, refer to the steps below.
16. ☐	Active NOAMP: Recover remaining failed SOAM Servers	Repeat Step 7 for any SOAM server that needs to be recovered.


Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

17. ☐	Active NOAMP: Set HA on all C-Level Servers	Navigate to Status & Manage → HA  Click on Edit at the bottom of the screen For each server whose Max Allowed HA Role is set to Standby, set it to Active Press OK
18. ☐	Recovered Servers: Login	Establish an SSH to the recovered server's XMI address:

Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

19.	Recovered Servers: Sync NTP	1) Perform the following to retrieve the remote NTP server: <pre>\$ sudo ntpq -np</pre> Example output: <pre>[admusr@NOAMP-2 ~]\$ ntpq -np</pre><table><tr><th>remote</th><th>refid</th><th>st</th><th>t</th><th>when</th><th>poll</th><th>reach</th><th>delay</th><th>offset</th></tr><tr><td>jitter</td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td></tr><tr><td colspan="9">=====</td></tr><tr><td colspan="9">=====</td></tr><tr><td>*10.240.9.186</td><td>10.250.33.2</td><td>3</td><td>u</td><td>356</td><td>1024</td><td>377</td><td>1.409</td><td>0.113</td></tr><tr><td>2.434</td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td></tr></table> 2) Stop ntpd service: <pre>\$ sudo service ntpd stop</pre> 3) Sync the date to the ntp remote server: <pre>\$ sudo ntpdate <NTP remote server></pre> Note: The remote server below will be that of the one gathered in sub step 1. 4) Start the ntp service: <pre>\$ sudo service ntpd start</pre>	remote	refid	st	t	when	poll	reach	delay	offset	jitter									=====									=====									*10.240.9.186	10.250.33.2	3	u	356	1024	377	1.409	0.113	2.434								
remote	refid	st	t	when	poll	reach	delay	offset																																																
jitter																																																								
=====																																																								
=====																																																								
*10.240.9.186	10.250.33.2	3	u	356	1024	377	1.409	0.113																																																
2.434																																																								

Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact


20. ☐	Active NOAMP: Restart UDR application on recovered servers	Navigate to Main Menu → Status & Manage → Server,  Select each recovered server and click on Restart. Stop Restart Reboot NTP Sync Report
21. ☐	Active NOAMP: Perform key exchange between the active-NOAMP and recovered servers.	Establish an SSH session to the Active NOAMP, login as <i>admusr</i>. Execute the following command to perform a keyexchange from the active NOAMP to each recovered server: <pre>\$ keyexchange admusr@<Recovered Server Hostname></pre> Note: If an export server is configured, perform this step.

Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

22.

Active NOAMP:
Fetch and Store
the database
Report for the
Newly Restored
Data and Save it

Navigate to **Main Menu → Status & Manage → Database**



Select the **active** NOAMP server and click on the **Report** button at the bottom of the page. The following screen is displayed:

Main Menu: Status & Manage -> Database [Report]

Report Generated: Tue Oct 05 15:13:38 2010 UTC
From: Active Network OAM&P on host blade07
Report Version: 3.0.13-3.0.0_10.13.0
User: guadmin

General

Hostname : blade07
Appworks Database Version : 3.0
Application Database Version :

Capacities and Utilization

Disk Utilization 0.6%: 249M used of 40G total, 38G available
Memory Utilization 0.6%: 136M used of 23975M total, 23839M available

Alarms

None

Maintenance in Progress

Restore operation success

Service Information

Part: A_NpqrProvPart

Table Name	Schema	Row Size		Num Rows	Memory		Disk	
		Avg	Max		Used	Alloc	Used	Alloc
CgPa		44		1	44 B	44 B	44 B	44 B
CgPaGta		52		0	0 B	0 B	0 B	0 B
CgPaInfo		64		1	64 B	64 B	64 B	64 B
CgPaOpc		36		0	0 B	0 B	0 B	0 B
CountryCode		24		306	7344 B	7344 B	7344 B	7344 B
GTConfig		52		2	104 B	104 B	104 B	104 B
MccMnc		40		0	0 B	0 B	0 B	0 B
Msisdn		52		0	0 B	0 B	0 B	0 B
Msrn		68		0	0 B	0 B	0 B	0 B
NpqrNeOptions		276		0	0 B	0 B	0 B	0 B

Print

Save

Click on **Save** and save the report to your local machine.

Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

23.	Active NOAMP: ☐ Verify Replication Between Servers.	Login to the Active NOAMP via SSH terminal as <i>admusr</i> user. Execute the following command: \$ sudo irepstat -m Output like below shall be generated: <pre>-- Policy 0 ActStb [DbReplication] ----- ----- RDU06-MP1 -- Stby BC From RDU06-SO1 Active 0 0.50 ^0.17%cpu 42B/s A=none CC From RDU06-MP2 Active 0 0.10 ^0.17 0.88%cpu 32B/s A=none RDU06-MP2 -- Active BC From RDU06-SO1 Active 0 0.50 ^0.10%cpu 33B/s A=none CC To RDU06-MP1 Active 0 0.10 0.08%cpu 20B/s A=none RDU06-NO1 -- Active AB To RDU06-SO1 Active 0 0.50 1%R 0.03%cpu 21B/s RDU06-SO1 -- Active AB From RDU06-NO1 Active 0 0.50 ^0.04%cpu 24B/s BC To RDU06-MP1 Active 0 0.50 1%R 0.04%cpu 21B/s BC To RDU06-MP2 Active 0 0.50 1%R 0.07%cpu 21B/s</pre>
-----	--	---


Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

24.

Active NOAMP:

Verify the Database states

Click on Main Menu → Status and Manager → Database



Verify that the “OAM Max HA Role” is either “Active” or “Standby” for NOAMP and SOAM and “Application Max HA Role” for MPs is “Active”, and that the status is “Normal” as shown below:


Network Element	Server	Role	OAM Max HA Role	Application Max HA Role	Status	DB Level	OAM Repl Status	SIG Repl Status	Repl Status	Repl Audit Status
NO_10303	NO2	Network OAM&P	Active	OOS	Normal	0	Normal	NotApplicabl	Allowed	AutoInProg
SO_10303	PSBR	MP	Active	Active	Normal	0	Normal	Normal	Allowed	AutoInProg
SO_10303	MP2	MP	Active	Active	Normal	0	Normal	Normal	Allowed	AutoInProg
SO_10303	SO1	System OAM	Standby	OOS	Normal	0	Normal	NotApplicabl	Allowed	AutoInProg
NO_10303	NO1	Network OAM&P	Standby	OOS	Normal	0	Normal	NotApplicabl	Allowed	AutoInProg
SO_10303	IPFE	MP	Active	OOS	Normal	0	Normal	Normal	Allowed	AutoInProg
SO_10303	SO2	System OAM	Active	OOS	Normal	0	Normal	NotApplicabl	Allowed	AutoInProg

25.

Active NOAMP:

Verify the HA Status

Click on Main Menu → Status and Manage → HA





Select the row for all of the servers



Verify that the “HA Role” is either “Active” or “Standby”.

Hostname	OAM Max HA Role	Application Max HA Role	Max Allowed HA Role	Mate Hostname List	Network Element	Server Role	Active VIPs
NO2	Active	OOS	Active	NO1	NO_10303	Network OAM&P	10.240.70.132
SO1	Standby	OOS	Active	SO2	SO_10303	System OAM	
SO2	Active	OOS	Active	SO1	SO_10303	System OAM	10.240.70.133
MP1	Standby	Active	Active	MP2	SO_10303	MP	
MP2	Active	Active	Active	MP1	SO_10303	MP	
IPFE	Active	OOS	Active		SO_10303	MP	




Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

26. ☐	Active SOAM: Verify the Local Node Info	Navigate to Main Menu → Diameter → Configuration → Local Node  Verify that all the local nodes are shown.
27. ☐	Active SOAM: Verify the Peer Node Info	Navigate to Main Menu → Diameter → Configuration → Peer Node  Verify that all the peer nodes are shown.

Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

28.	Active SOAM: Verify the Connections Info	Navigate to Main Menu → Diameter → Configuration → Connections  Verify that all the connections are shown.
29.	Active SOAM: Enable Connections if needed	Navigate to Main Menu → Diameter → Maintenance → Connections  Select each connection and click on the Enable button. Alternatively you can enable all the connections by selecting the EnableAll button. Enable Disable EnableAll DisableAll Diagnose Start Diagnose End SCTP STATISTICS ☐ Pause updates Verify that the Operational State is Available.

Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

30. ☐	Active SOAM: Enable Optional Features	Navigate to Main Menu → Diameter → Maintenance → Applications  Select the SPR feature application. Click the Enable button. Enable Disable ☐ Pause updates
31. ☐	Active SOAM: Examine All Alarms	Navigate to Main Menu → Alarms & Events → View Active  Examine all active alarms and refer to the on-line help on how to address them. If needed contact My Oracle Support (MOS).
32. ☐	Active NOAMP: Examine All Alarms	Login to the NOAMP VIP if not already logged in. Navigate to Main Menu → Alarms & Events → View Active  Examine all active alarms and refer to the on-line help on how to address them. If needed contact My Oracle Support (MOS).
33. ☐	Restore GUI Username and Passwords	If applicable, Execute steps in Section 5 to recover the user and group information restored.

Procedure 3: Recovery Scenario 3 – Partial Outage One SOAM Intact

34. ☐	Backup and Archive All the Databases from the Recovered System	Execute Appendix A Oracle Communications User Data Repository Database Backup to back up the Configuration databases.
THIS PROCEDURE HAS BEEN COMPLETED		

4.1.4 Recovery Scenario 4 (Partial Server Outage with one NOAMP server and one SOAM server intact)

For a partial outage with an NOAMP server and an SOAM server intact and available, only base recovery of software is needed. The intact NO and SOAM servers are capable of restoring the database via replication to all servers. The major activities are summarized in the list below. Use this list to understand the recovery procedure summary. Do not use this list to execute the procedure. The actual procedures' detailed steps are in Procedure 4. The major activities are summarized as follows:

Recover Standby NOAMP server by recovering software.

- Recover the software.


The database is intact at the active NOAMP server and does not require restoration at the standby NOAMP server.

- Recover any failed SO and MP servers by recovering software.
- Recover the software.

The database is intact at the active NOAMP server and does not require restoration at the SO and MP servers.

- Re-apply signaling networks configuration if the failed VM is an MP.


Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

S T E P #	This procedure performs recovery if at least 1 NOAMP server is intact and available and 1 SOAM server is intact and available. Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number. If this procedure fails, contact My Oracle Support (MOS), and ask for assistance.	
1. ☐	Gather Required Materials	Gather the documents and required materials listed in Section 3.1 Required Materials
2. ☐	Active NOAMP: Login	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of: http://<Primary_NOAMP_VIP_IP_Address> Login as the guiadmin user: 
3. ☐	Active NOAMP: Set Failed Servers to Standby	Navigate to Main Menu → Status & Manage → HA  Select Edit Set the Max Allowed HA Role drop down box to Standby for the failed servers. Select Ok Ok Cancel

Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

4. ☐	Recover the Failed Software	Execute the following procedures from reference <i>Oracle Communications User Data Repository 12.11 Cloud Installation and Configuration Guide, latest revision</i> [2]: Procedure 2 : Deploy Oracle Communications User Data Repository Virtual Machines on VMware
5. ☐	Repeat for Remaining Failed Servers	If necessary, repeat 4 for all remaining failed servers.
6. ☐	Active NOAMP: Login	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of: http://<Primary_NOAMP_VIP_IP_Address> Login as the guiadmin user: 
7. ☐	Active NOAMP: Recover Standby NOAMP if needed	Configure the second NOAMP server by executing procedures from reference <i>Oracle Communications User Data Repository 12.11 Cloud Installation and Configuration Guide, latest revision</i> [2]: Procedure 4 “Create Configuration for Remaining Servers”, Step 2. Procedure 10 “Apply Configuration for Remaining Servers” Note: If Topology or nodeId alarms are persistent after the database restore, refer to the steps below.





Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

8. ☐	Active NOAMP: Recover the Failed SOAM Servers if needed	Repeat Step 7 for any SOAM server that needs to be recovered.
9. ☐	Active NOAMP: Set HA on Recovered Servers	Navigate to Status & Manage → HA  Click on Edit at the bottom of the screen For each server whose Max Allowed HA Role is set to Standby, set it to Active Press OK
10.	Recovered Servers: Login	Establish an SSH to the recovered server's XMI address:


Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

11.	Recovered Servers: Sync NTP	1) Perform the following to retrieve the remote NTP server: <pre>\$ sudo ntpq -np</pre> Example output: <pre>[admusr@NOAMP-2 ~]\$ ntpq -np</pre><table><thead><tr><th>remote</th><th>refid</th><th>st</th><th>t</th><th>when</th><th>poll</th><th>reach</th><th>delay</th><th>offset</th></tr></thead><tbody><tr><td>jitter</td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td></tr><tr><td colspan="9">=====</td></tr><tr><td colspan="9">=====</td></tr><tr><td>*10.240.9.186</td><td>10.250.33.2</td><td>3</td><td>u</td><td>356</td><td>1024</td><td>377</td><td>1.409</td><td>0.113</td></tr><tr><td>2.434</td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td></tr></tbody></table> 2) Stop ntpd service: <pre>\$ sudo service ntpd stop</pre> 3) Sync the date to the ntp remote server: <pre>\$ sudo ntpdate <NTP remote server></pre> Note: The remote server below will be that of the one gathered in sub step 1. 4) Start the ntp service: <pre>\$ sudo service ntpd start</pre>	remote	refid	st	t	when	poll	reach	delay	offset	jitter									=====									=====									*10.240.9.186	10.250.33.2	3	u	356	1024	377	1.409	0.113	2.434								
remote	refid	st	t	when	poll	reach	delay	offset																																																
jitter																																																								
=====																																																								
=====																																																								
*10.240.9.186	10.250.33.2	3	u	356	1024	377	1.409	0.113																																																
2.434																																																								

Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

12.	Active NOAMP: Restart UDR application on recovered SOAM	Navigate to Main Menu → Status & Manage → Server  Select the recovered server and click on Restart. 
13. ☐	Active NOAMP: Recover MP Servers	Recover the MP server(s) by executing procedures from reference <i>Oracle Communications User Data Repository 12.11 Cloud Installation and Configuration Guide, latest revision</i> [2]: Procedure 4 “Create Configuration for Remaining Servers”, Step 2 Procedure 10 “Apply Configuration for Remaining Servers” for MP(s)
14. ☐	Active NOAMP: Restart UDR Application on recovered MP servers.	Navigate to Main Menu → Status & Manage → Server  Select the recovered servers and click on Restart. 

Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

15. ☐	Active NOAMP: Set HA on all MP servers	Navigate to Status & Manage → HA  Click on Edit at the bottom of the screen For each server whose Max Allowed HA Role is set to Standby, set it to Active Press OK
16. ☐	Active NOAMP: Login	Login to the recovered Active NOAMP via SSH terminal as <i>admusr</i> user.
17. ☐	Active NOAMP: Perform key exchange between the active-NOAMP and recovered servers.	Establish an SSH session to the Active NOAMP, login as <i>admusr</i>. Execute the following command to perform a keyexchange from the active NOAMP to each recovered server: <pre>\$ keyexchange admusr@<Recovered Server Hostname></pre>
18. ☐	Active NOAMP: Establish SSH	Establish an SSH session to the active NOAMP, login as <i>admusr</i> .


Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

19.

Active NOAMP:

Fetch and Store the database Report for the Newly Restored Data and Save it

Navigate to **Main Menu → Status & Manage → Database**



Select the **active** NOAMP server and click on the **Report** button at the bottom of the page. The following screen is displayed:

Main Menu: Status & Manage -> Database [Report]

Tue Oct 05 15:13:38 2010 UTC

Help

=====

NPQR Database Status Report

=====

Report Generated: Tue Oct 05 15:13:38 2010 UTC

From: Active Network OAM&P on host blade07

Report Version: 3.0.13-3.0.0_10.13.0

User: guidadmin

=====

General

Hostname : blade07

Appworks Database Version : 3.0

Application Database Version :

Capacities and Utilization

Disk Utilization 0.6%: 249M used of 40G total, 38G available

Memory Utilization 0.6%: 136M used of 23975M total, 23839M available

Alarms

None

Maintenance in Progress

Restore operation success

Service Information

Part: A_NpqrProvPart

Table Name	Schema	Row Size Avg Max	Num Rows	Memory Used / Alloc	Disk Used / Alloc
CgPa		44	1	44 B	44 B
CgPaGta		52	0	0 B	0 B
CgPaInfo		64	1	64 B	64 B
CgPaOpc		36	0	0 B	0 B
CountryCode		24	306	7344 B	7344 B
GTConfig		52	2	104 B	104 B
MccMnc		40	0	0 B	0 B
Msisdn		52	0	0 B	0 B
Msrn		68	0	0 B	0 B
NpqrNeOptions		276	0	0 B	0 B



=====

Print


Save

Click on **Save** and save the report to your local machine.



Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

22. 	Active NOAMP: Verify the HA Status	Click on Main Menu → Status and Manage → HA  Select the row for all of the servers Verify that the “HA Role” is either “Active” or “Standby”. <table><thead><tr><th>Hostname</th><th>OAM Max HA Role</th><th>Application Max HA Role</th><th>Max Allowed HA Role</th><th>Mate Hostname List</th><th>Network Element</th><th>Server Role</th><th>Active VIPs</th></tr></thead><tbody><tr><td>NO2</td><td>Active</td><td>OOS</td><td>Active</td><td>NO1</td><td>NO_10303</td><td>Network OAM&P</td><td>10.240.70.132</td></tr><tr><td>SO1</td><td>Standby</td><td>OOS</td><td>Active</td><td>SO2</td><td>SO_10303</td><td>System OAM</td><td></td></tr><tr><td>SO2</td><td>Active</td><td>OOS</td><td>Active</td><td>SO1</td><td>SO_10303</td><td>System OAM</td><td>10.240.70.133</td></tr><tr><td>MP1</td><td>Standby</td><td>Active</td><td>Active</td><td>MP2</td><td>SO_10303</td><td>MP</td><td></td></tr><tr><td>MP2</td><td>Active</td><td>Active</td><td>Active</td><td>MP1</td><td>SO_10303</td><td>MP</td><td></td></tr><tr><td>IPFE</td><td>Active</td><td>OOS</td><td>Active</td><td></td><td>SO_10303</td><td>MP</td><td></td></tr></tbody></table>	Hostname	OAM Max HA Role	Application Max HA Role	Max Allowed HA Role	Mate Hostname List	Network Element	Server Role	Active VIPs	NO2	Active	OOS	Active	NO1	NO_10303	Network OAM&P	10.240.70.132	SO1	Standby	OOS	Active	SO2	SO_10303	System OAM		SO2	Active	OOS	Active	SO1	SO_10303	System OAM	10.240.70.133	MP1	Standby	Active	Active	MP2	SO_10303	MP		MP2	Active	Active	Active	MP1	SO_10303	MP		IPFE	Active	OOS	Active		SO_10303	MP	
Hostname	OAM Max HA Role	Application Max HA Role	Max Allowed HA Role	Mate Hostname List	Network Element	Server Role	Active VIPs																																																			
NO2	Active	OOS	Active	NO1	NO_10303	Network OAM&P	10.240.70.132																																																			
SO1	Standby	OOS	Active	SO2	SO_10303	System OAM																																																				
SO2	Active	OOS	Active	SO1	SO_10303	System OAM	10.240.70.133																																																			
MP1	Standby	Active	Active	MP2	SO_10303	MP																																																				
MP2	Active	Active	Active	MP1	SO_10303	MP																																																				
IPFE	Active	OOS	Active		SO_10303	MP																																																				
23. 	Active SOAM: Verify the Local Node Info	Navigate to Main Menu → Diameter → Configuration → Local Node  Verify that all the local nodes are shown.																																																								




Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

24. ☐	Active SOAM: Verify the Peer Node Info	Navigate to Main Menu → Diameter → Configuration → Peer Node A screenshot of a web-based configuration interface. At the top, there is a breadcrumb trail: 'Diameter' > 'Configuration'. Below this, a list of configuration items is displayed. The items are: Capacity Summary, Connection Capacity Dashboard, Application Ids, CEX Parameters, Command Codes, Configuration Sets, Local Nodes, Peer Nodes (which is highlighted with a blue background), Peer Node Groups, Connections, Route Groups, Route Lists, Peer Route Tables, Egress Throttle Groups, Reroute On Answer, Application Route Tables, Routing Option Sets, Pending Answer Timers, System Options, and DNS Options. Verify that all the peer nodes are shown.
--	--	--

Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

25. ☐	Active SOAM: Verify the Connections Info	Navigate to Main Menu → Diameter → Configuration → Connections  Verify that all the connections are shown.
26. ☐	Active SOAM: Enable Connections if needed	Navigate to Main Menu → Diameter → Maintenance → Connections  Select each connection and click on the Enable button. Alternatively you can enable all the connections by selecting the EnableAll button. Enable Disable EnableAll DisableAll Diagnose Start Diagnose End SCTP STATISTICS ☐ Pause updates Verify that the Operational State is Available.

Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

27. ☐	Active SOAM: Enable Optional Features	Navigate to Main Menu → Diameter → Maintenance → Applications  Select the SPR feature applications. Click the Enable button. Enable Disable ☐ Pause updates
28. ☐	Active SOAM: Examine All Alarms	Navigate to Main Menu → Alarms & Events → View Active  Examine all active alarms and refer to the on-line help on how to address them. If needed contact My Oracle Support (MOS).
29. ☐	Active NOAMP: Examine All Alarms	Login to the NOAMP VIP if not already logged in. Navigate to Main Menu → Alarms & Events → View Active  Examine all active alarms and refer to the on-line help on how to address them. If needed contact My Oracle Support (MOS).

Procedure 4: Recovery Scenario 4 – Partial Outage One NOAMP & One SOAM Intact

30. ☐	Restart oampAgent if Needed	Note: If alarm “10012: The responder for a monitored table failed to respond to a table change” is raised, the oampAgent needs to be restarted. Establish an SSH session to each server that has the alarm. Login as <i>admusr</i> Execute the following commands: <pre>\$ sudo pm.set off oampAgent \$ sudo pm.set on oampAgent</pre>
31. ☐	Backup and Archive All the Databases from the Recovered System	Execute Appendix A Oracle Communications User Data Repository Database Backup to back up the Configuration databases.
THIS PROCEDURE HAS BEEN COMPLETED		

4.1.5 Recovery Scenario 5 (Database Recovery)

The following sections deal with recovering from database corruption, whether a backup is present or not.



4.1.5.1 Recovery Scenario 5: Case 1

For a partial outage with


- Server having a corrupted database
- Replication channel from parent is inhibited because of upgrade activity or
- Server is in a different release then that of its Active parent because of upgrade activity.
- Verify that the Server Runtime backup files, performed at the start of the upgrade, are present in /var/TKLC/db/filemgmt area in the following format
 - Backup.UDR.HPC02-NO2.FullDBParts.NETWORK_OAMP.20140524_223507.UPG.tar.bz2
 - Backup.UDR.HPC02-NO2.FullRunEnv.NETWORK_OAMP.20140524_223507.UPG.tar.bz2

Note: During recovery, the corrupted Database will get replaced by the sever Runtime backup. Any configuration done after taking the backup will not be visible post recovery.

Procedure 5: Recovery Scenario 5 (Case 1) – Database Recovery Backup Present

S T E P #	This procedure performs recovery if database is corrupted in the system Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number. If this procedure fails, contact My Oracle Support (MOS), and ask for assistance.	
1. ☐	Active NOAMP: Set Failed Servers to Standby	Navigate to Main Menu → Status & Manage → HA  Select Edit Set the Max Allowed HA Role drop down box to Standby for the failed servers. Select Ok 
2. ☐	Server with DB Corruption: Login	Establish an SSH session to the server in question. Login as <i>admusr</i> user.
3. ☐	Server with DB Corruption: Change runlevel to 3	Execute the following command to bring the system to runlevel 3. <pre>\$ sudo init 3</pre>

Procedure 5: Recovery Scenario 5 (Case 1) – Database Recovery Backup Present



4. ☐	Server with DB Corruption: Recover System	Execute the following command and follow the instructions appearing the console prompt <pre>\$ sudo /usr/TKLC/appworks/sbin/backout_restore</pre>
5. ☐	Server with DB Corruption: Change runlevel to 4	Execute the following command to bring the system back to runlevel 4. <pre>\$ sudo init 4</pre>
6. ☐	Server with DB Corruption: Verify the server	Execute the following command to verify if the processes are up and running <pre>\$ sudo pm.getprocs</pre>
7. ☐	Active NOAMP: Set Failed Servers to Active	Navigate to Status & Manage → HA  Click on Edit at the bottom of the screen For each failed server whose Max Allowed HA Role is set to Standby, set it to Active Press OK
8. ☐	Backup and Archive All the Databases from the Recovered System	Execute Appendix A Oracle Communications User Data Repository Database Backup to back up the Configuration databases:
THIS PROCEDURE HAS BEEN COMPLETED		

4.1.5.2 Recovery Scenario 5: Case 2


For a partial outage with

- Server having a corrupted database
- Replication channel is available or
- Server has the same release as that of its Active parent


Procedure 6: Recovery Scenario 5 (Case 2) – Database Recovery Backup Not Present

S T E P #		This procedure performs recovery if database got corrupted in the system and system is in the state to get replicated Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number. If this procedure fails, contact My Oracle Support (MOS) , and ask for assistance.
1. ☐	Active NOAMP: Set Failed Servers to Standby	Navigate to Main Menu → Status & Manage → HA  Select Edit Set the Max Allowed HA Role drop down box to Standby for the failed servers. Select Ok 
2. ☐	Server with DB Corruption: Login	Establish an SSH session to the server in question. Login as admusr user.
3. ☐	Server with DB Corruption: Take Server out of Service	Execute the following command to take the server out of service. <pre>\$ sudo bash -l \$ sudo prod.clobber</pre>
4. ☐	Server with DB Corruption: Take Server to DbUp State and Start the Application	Execute the following commands to take the server to Dbup and start the Oracle Communications User Data Repository application: <pre>\$ sudo bash -l \$ sudo prod.start</pre>

Procedure 6: Recovery Scenario 5 (Case 2) – Database Recovery Backup Not Present

5. ☐	Server with DB Corruption: Verify the Server State	Execute the following commands to verify the processes are up and running: <code>\$ sudo pm.getprocs</code> Execute the following command to verify if replication channels are up and running: <code>\$ sudo irepstat</code> Execute the following command to verify if merging channels are up and running: <code>\$ sudo inetmstat</code>
6. ☐	Active NOAMP: Restart UDR application	Navigate to Main Menu → Status & Manage → Server  Select each recovered server and click on Restart. Stop Restart Reboot NTP Sync Report

Procedure 6: Recovery Scenario 5 (Case 2) – Database Recovery Backup Not Present

7. ☐	Active NOAMP: Set Failed Servers to Active	Navigate to Status & Manage → HA  Click on Edit at the bottom of the screen For each failed server whose Max Allowed HA Role is set to Standby, set it to Active Press OK
8. ☐	Backup and Archive All the Databases from the Recovered System	Execute Appendix A Oracle Communications User Data Repository Database Backup to back up the Configuration databases:
THIS PROCEDURE HAS BEEN COMPLETED		

5 RESOLVING USER CREDENTIAL ISSUES AFTER DATABASE RESTORE

User incompatibilities may introduce security holes or prevent access to the network by administrators. User incompatibilities are not dangerous to the database, however. Review each user difference carefully to ensure that the restoration will not impact security or accessibility.


5.1 Keeping a Restored User (Resetting User Password)

User accounts kept across a restore operation should have their passwords reset. This procedure guides you through that process.

Procedure 7: Keep Restored User (Resetting User Password)

S T E P #	Perform this procedure to keep users that will be restored by system restoration. Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number. If this procedure fails, contact My Oracle Support (MOS), and ask for assistance.
1. ☐	Before Restoration: Notify Affected Users <i>(Before Restoration)</i> Contact each user that is affected <u>before the restoration</u> and notify them that you will reset their password during this maintenance operation.
2. ☐	After Restoration: Login to the Active NOAMP <i>(Before Restoration)</i> Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of: http://<Primary_NOAMP_VIP_IP_Address> Login as the guiadmin user:  Welcome to the Oracle System Login. Unauthorized access is prohibited. This Oracle system requires the use of Microsoft Internet Explorer 8.0, 9.0, or 10.0 with support for JavaScript and cookies. Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

Procedure 7: Keep Restored User (Resetting User Password)


3.	After Restoration: Reset User Passwords	Navigate to Administration → Access Control → Users  Select the user Click the Change Password button  Enter a new password  Click the Continue button
THIS PROCEDURE HAS BEEN COMPLETED		

5.2 Removing a Restored User

Procedure 8: Remove the Restored User

S T E P #	Perform this procedure to remove users that will be restored by system restoration Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number. If this procedure fails, contact My Oracle Support (MOS), and ask for assistance.
1. ☐	After Restoration: Login to the Active NOAMP Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of: http://<Primary_NOAMP_VIP_IP_Address> Login as the <i>guiadmin</i> user: ORACLE® Oracle System Login Fri Mar 20 12:29:52 2015 EDT Log In Enter your username and password to log in Username: guiadmin Password: •••••• ☐ Change password Log In Welcome to the Oracle System Login. Unauthorized access is prohibited. This Oracle system requires the use of Microsoft Internet Explorer 8.0, 9.0, or 10.0 with support for JavaScript and cookies. Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

Procedure 8: Remove the Restored User

2. 	After Restoration: Delete User	Navigate to Administration → Access Control → Users  Select the user Click the Delete button Insert Edit Delete Report Change Password Delete selected users? OK Cancel Click the OK button to confirm.
THIS PROCEDURE HAS BEEN COMPLETED		

5.3 Restoring a Modified User

These users have had a password change prior to creation of the backup and archive file. The will be reverted by system restoration of that file.

- The password for user 'testuser' differs between the selected backup file and the current database.

Before Restoration:

Verify that you have access to a user with administrator permissions that is not affected.

Contact each user that is affected and notify them that you will reset their password during this maintenance operation.

After Restoration:

Log in and reset the passwords for all users in this category. See the steps in Section 5.1 (Keeping a Restored User) for resetting passwords for a user.

5.4 Restoring an Archive that does not contain a Current User


These users have been created after the backup operation. They will be deleted by system restoration of that file.

If the user is no longer desired, do not perform any additional steps. The user is permanently removed.


Procedure 9: Restoring an Archive that does not Contain a Current User

S T E P #	Perform this procedure to remove users that will be restored by system restoration Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number. If this procedure fails, contact My Oracle Support (MOS) , and ask for assistance.	
1. ☐	Before Restoration: Notify Affected Users (Before Restoration)	Contact each user that is affected <u>before the restoration</u> and notify them that you will reset their password during this maintenance operation.
2. ☐	Before Restoration: Login to the Active NOAMP (Before Restoration)	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of: http://<Primary_NOAMP_VIP_IP_Address> Login as the guiadmin user: 

Procedure 9: Restoring an Archive that does not Contain a Current User

3. ☐	Before Restoration: Record user settings <i>(Before Restoration)</i>	Navigate to Administration → Access Control → Users  Under each affected user, record the following: • Username, • Account status • Remote Auth • Local Auth • Concurrent Logins Allowed • Inactivity Limit • Comment • Groups
4. ☐	After Restoration: Login	Establish a GUI session on the NOAMP server by using the VIP IP address of the NOAMP server. Open the web browser and enter a URL of: <code>http://<Primary_NOAMP_VIP_IP_Address></code> Login as the guiadmin user: 

Procedure 9: Restoring an Archive that does not Contain a Current User

5. 	After Restoration: Recreate affected user	Navigate to Administration → Access Control → Users  Click Insert Insert Edit Delete Report Change Password Recreate the user using the data collected in Step 3. Username * Group admin * Authentication Options ☐ Allow Remote Auth ☒ Allow Local Auth Access Allowed ☒ Account Enabled Maximum Concurrent Logins 0 Session Inactivity Limit 120 Comment *
-------------------	--	---


Click **Ok**

Ok

Apply

Cancel

Procedure 9: Restoring an Archive that does not Contain a Current User

7. ☐	After Restoration: Reset the Passwords	Navigate to Administration → Access Control → Users  Select the user Click the Change Password button Insert Edit Delete Report Change Password Enter a new password Enter the new password for guiadmin two times. New Password: Retype New Password: ☒ Force password change on next login Continue Click the Continue button
THIS PROCEDURE HAS BEEN COMPLETED		

Appendix A. Oracle Communications User Data Repository Database Backup

Procedure 12: Restoring an Archive that does not Contain a Current User


S T E P #	The intent of this procedure is to back up the provision and configuration information from an NOAMP or SOAM server after the disaster recovery is complete Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number. If this procedure fails, contact My Oracle Support (MOS), and ask for assistance.
1. 	Establish a GUI session on the Active NOAMP or SOAM server by using the VIP IP address of the NOAMP or SOAM server. Open the web browser and enter a URL of: http://<Primary_NOAMP/SOAM_VIP_IP_Address> Login as the <i>guiadmin</i> user: ORACLE® Oracle System Login Fri Mar 20 12:29:52 2015 EDT Log In Enter your username and password to log in Username: guiadmin Password: •••••• ☐ Change password Log In Welcome to the Oracle System Login. Unauthorized access is prohibited. This Oracle system requires the use of Microsoft Internet Explorer 8.0, 9.0, or 10.0 with support for JavaScript and cookies. Oracle and Java are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

Procedure 12: Restoring an Archive that does not Contain a Current User


2.

Active NOAMP/SOAM: Backup Configuration Data for the System

Navigate to **Main Menu** → **Status & Manage** → **Database**



Select the Active NOAMP Server and Click on **Backup** button




Make sure that the checkboxes next to “Configuration” is checked.

Database Backup

Field	Value
Server: Jetta-NO-1	
Select data for backup	☐ Provisioning ☒ Configuration
Compression	☐ gzip ☒ bzip2 ☐ none *
Archive Name	Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP.20150428_09311: *
Comment	

Enter a filename for the backup and press **OK**

Procedure 12: Restoring an Archive that does not Contain a Current User


3. ☐	Active NOAMP/SOAM: Verify the backup file existence.	Navigate to Main Menu → Status & Manage → Files  Main Menu: Status & Manage -> Files Filter ▾Tasks ▾ Jetta-NO-1Jetta-NO-2Jetta-SO-1Jetta-SO-2Jetta-DAMP-1Jetta-DAMP-2 <table><tr><th>File Name</th></tr><tr><td>Backup.DSR.Jetta-NO-1.FullDBParts.NETWORK_OAMP20150421_143846.UPG.tar.bz2</td></tr><tr><td>Backup.DSR.Jetta-NO-1.FullRunEnv.NETWORK_OAMP20150421_143846.UPG.tar.bz2</td></tr><tr><td>backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150414_021511.AUTO.tar</td></tr><tr><td>backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150415_021510.AUTO.tar</td></tr><tr><td>backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150416_021511.AUTO.tar</td></tr><tr><td>backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150417_021510.AUTO.tar</td></tr><tr><td>backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150418_021510.AUTO.tar</td></tr><tr><td>backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150419_021510.AUTO.tar</td></tr><tr><td>backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150420_021510.AUTO.tar</td></tr><tr><td>backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150421_021511.AUTO.tar</td></tr><tr><td>backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150422_021511.AUTO.tar</td></tr><tr><td>backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150423_021510.AUTO.tar</td></tr><tr><td>backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150424_021511.AUTO.tar</td></tr><tr><td>backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150425_021510.AUTO.tar</td></tr><tr><td>backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150426_021510.AUTO.tar</td></tr><tr><td>backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150427_021511.AUTO.tar</td></tr><tr><td>backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150428_021511.AUTO.tar</td></tr></table> Select the Active NOAMP or SOAM tab. The files on this server will be displayed. Verify the existence of the backup file.	File Name	Backup.DSR.Jetta-NO-1.FullDBParts.NETWORK_OAMP20150421_143846.UPG.tar.bz2	Backup.DSR.Jetta-NO-1.FullRunEnv.NETWORK_OAMP20150421_143846.UPG.tar.bz2	backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150414_021511.AUTO.tar	backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150415_021510.AUTO.tar	backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150416_021511.AUTO.tar	backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150417_021510.AUTO.tar	backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150418_021510.AUTO.tar	backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150419_021510.AUTO.tar	backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150420_021510.AUTO.tar	backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150421_021511.AUTO.tar	backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150422_021511.AUTO.tar	backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150423_021510.AUTO.tar	backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150424_021511.AUTO.tar	backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150425_021510.AUTO.tar	backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150426_021510.AUTO.tar	backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150427_021511.AUTO.tar	backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150428_021511.AUTO.tar
File Name																				
Backup.DSR.Jetta-NO-1.FullDBParts.NETWORK_OAMP20150421_143846.UPG.tar.bz2																				
Backup.DSR.Jetta-NO-1.FullRunEnv.NETWORK_OAMP20150421_143846.UPG.tar.bz2																				
backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150414_021511.AUTO.tar																				
backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150415_021510.AUTO.tar																				
backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150416_021511.AUTO.tar																				
backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150417_021510.AUTO.tar																				
backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150418_021510.AUTO.tar																				
backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150419_021510.AUTO.tar																				
backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150420_021510.AUTO.tar																				
backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150421_021511.AUTO.tar																				
backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150422_021511.AUTO.tar																				
backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150423_021510.AUTO.tar																				
backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150424_021511.AUTO.tar																				
backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150425_021510.AUTO.tar																				
backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150426_021510.AUTO.tar																				
backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150427_021511.AUTO.tar																				
backup/Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP20150428_021511.AUTO.tar																				

Procedure 12: Restoring an Archive that does not Contain a Current User

4. ☐	Active NOAMP/SOAM: Download the file to a local machine.	From the previous step, choose the backup file. Select the Download button Delete View Upload Download Deploy ISO Validate ISO 1.1 GB used (5.93%) of 18.4 GB available System utilization: 1.1 GB (5.99%) of 18.4 GB available. Select OK to confirm the download. Opening Backup.dsr.Jetta-NO-1.Configuration.NETWORK_OAMP.2015... You have chosen to open: ...1.Configuration.NETWORK_OAMP.20150418_021510.AUTO.tar which is: tar Archive (13.5 MB) from: https://100.65.209.143 What should Firefox do with this file? ☒ Open with 7-Zip File Manager (default) ☐ Save File ☐ Do this automatically for files like this from now on. OK Cancel
5. ☐	Upload the Image to Secure Location	Transfer the backed up image saved in the previous step to a secure location where the Server Backup files are fetched in case of system disaster recovery.
6. ☐	Backup Active SOAM	Repeat Steps 2 through 5 to back up the Active SOAM.
THIS PROCEDURE HAS BEEN COMPLETED		

Appendix B. Inhibit A and B Level Replication on C-Level Servers

Procedure 13: Inhibit A and B Level Replication on C-Level Servers

S T E P #	The intent of this procedure is to inhibit A and B level replication on all C Level servers of this site Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number. If this procedure fails, contact My Oracle Support (MOS) , and ask for assistance.	
1. ☐	Active NOAMP: Login	Login to the Active NOAMP server via SSH as <i>admusr</i> user.
2. ☐	Active NOAMP: Inhibit replication on all MP servers	Execute the following command: <pre>\$ for i in \$(iqt -p -z -h -fhostName NodeInfo where "nodeId like 'C*' and siteId='<NE name of the site>'"); do iset -finhibitRepPlans='A B' NodeInfo where "nodeName='\$i'"; done</pre> Note: NE name of the site can be found out by logging into the Active NOAMP GUI and going to Configuration → Server Groups screen. Please see the snapshot below for more details. E.g. if ServerSO1 belong to the site which is being recovered then siteId will be SO_HPC03.  The screenshot shows the 'Main Menu: Configuration -> Server Groups' screen. It features a table with columns: Server Group Name, Level, Parent, Function, NE, Server, HA Role Pref, and VIPs. The table lists three server groups: MPSC, NOSG, and SOSG. The SOSG group is highlighted in green. Within the SOSG group, the 'NE' column shows 'SO_HPC03' circled in red, indicating the siteId for the site being recovered.

Procedure 13: Inhibit A and B Level Replication on C-Level Servers

3

Active NOAMP:
Verify Replication
has been
Inhibited.

After executing above steps to inhibit replication on MP(s), no alarms on GUI would be raised informing that replication on MP is disabled.

Verification of replication inhibition on MPs can be done by analyzing NodeInfo output. InhibitRepPlans field for all the MP servers for the selected site e.g. Site SO_HPC03 shall be set as 'A B':

Perform the following command:

\$ sudo iqt NodeInfo


Expected output:

nodeId	nodeName	hostName	nodeCapability	inhibitRepPlans	siteId	excludeTables
A1386.099	NO1	NO1	Active		NO	HPC03
B1754.109	SO1	SO1	Active		SO_HPC03	
C2254.131	MP2	MP2	Active	A B	SO_HPC03	
C2254.233	MP1	MP1	Active	A B	SO_HPC03	

THIS PROCEDURE HAS BEEN COMPLETED

Appendix C. Un-Inhibit A and B Level Replication on C-Level Servers

Procedure 14: Un-Inhibit A and B Level Replication on C-Level Servers

STEP #	The intent of this procedure is to Un-inhibit A and B level replication on all C Level servers of this site	
	Check off (✓) each step as it is completed. Boxes have been provided for this purpose under each step number.	
	If this procedure fails, contact My Oracle Support (MOS) , and ask for assistance.	
1. ☐	Active NOAMP: Login	Login to the Active NOAMP server via SSH as <i>admusr</i> user.
2. ☐	Active NOAMP: Un-Inhibit replication on all C level Servers	Execute the following command: <pre>\$ for i in \$(iqt -p -z -h -fhostName NodeInfo where "nodeId like 'C*' and siteId='<NE name of the site>'); do iset -finhibitRepPlans='' NodeInfo where "nodeName='\$i'; done</pre> Note: NE name of the site can be found out by logging into the Active NOAMP GUI and going to Configuration → Server Groups screen. Please see the snapshot below for more details. E.g. if ServerSO1 belong to the site which is being recovered then siteId will be SO_HPC03. Main Menu: Configuration -> Server Groups 

Procedure 14: Un-Inhibit A and B Level Replication on C-Level Servers

3.

Active NOAMP:
Verify Replication
has been
Inhibited.

After executing above steps to un-inhibit replication on MP(s), no alarms on GUI would be raised informing that replication on MP is disabled.

Verification of replication un-inhibition on MPs can be done by analyzing NodeInfo output. InhibitRepPlans field for all the MP servers for the selected site e.g. Site SO_HPC03 shall be set as 'A B':

Perform the following command:

\$ sudo iqt NodeInfo

Expected output:

nodeId	nodeName	hostName	nodeCapability	inhibitRepPlans	siteId	excludeTables
A1386.099	NO1	NO1	Active		NO_HPC03	
B1754.109	SO1	SO1	Active		SO_HPC03	
C2254.131	MP2	MP2	Active		SO_HPC03	
C2254.233	MP1	MP1	Active		SO_HPC03	

THIS PROCEDURE HAS BEEN COMPLETED

Appendix D. My Oracle Support (MOS)

MOS (<https://support.oracle.com>) is your initial point of contact for all product support and training needs. A representative at Customer Access Support (CAS) can assist you with MOS registration.

Call the CAS main number at **1-800-223-1711** (toll-free in the US), or call the Oracle Support hotline for your local country from the list at <http://www.oracle.com/us/support/contact/index.html>. When calling, make the selections in the sequence shown below on the Support telephone menu:

Select **2** for New Service Request

Select **3** for Hardware, Networking and Solaris Operating System Support

Select one of the following options:

- For Technical issues such as creating a new Service Request (SR), Select **1**
- For Non-technical issues such as registration or assistance with MOS, Select **2**

You will be connected to a live agent who can assist you with MOS registration and opening a support ticket.

MOS is available 24 hours a day, 7 days a week, 365 days a year.

Appendix E. Locate Product Documentation on the Oracle Help Center Site

Oracle Communications customer documentation is available on the web at the Oracle Help Center (OHC) site, <http://docs.oracle.com>. You do not have to register to access these documents. Viewing these files requires Adobe Acrobat Reader, which can be downloaded at <http://www.adobe.com>.

1. Access the Oracle Help Center site at <http://docs.oracle.com>
2. Click **Industries**.
3. Under the Oracle Communications subheading, click the **Oracle Communications documentation** link.
The Communications Documentation page appears. Most products covered by these documentation sets will appear under the headings “Network Session Delivery and Control Infrastructure” or “Platforms.”
4. Click on your Product and then the Release Number.
A list of the entire documentation set for the selected product and release appears.
5. To download a file to your location, right-click the **PDF** link, select **Save target as** (or similar command based on your browser), and save to a local folder.