

Oracle® Communications Network Charging and Control

Subscriber Event Service User's and Technical Guide



Release 15.0.0

October 2023

ORACLE®

Copyright

Copyright © 2023, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

About This Document	v
Document Conventions	vi
Chapter 1	
System Overview	1
Overview	1
Subscriber Event Service	1
Chapter 2	
Getting Started	13
Overview	13
Accessing Subscriber Event Service Configuration	13
Chapter 3	
SES Configuration Screens	17
Overview	17
Messages	17
Inbound General Messages	21
Inbound Messages	23
Outbound General Messages	25
Outbound Messages	28
Trigger Rules	30
Contact History	36
Chapter 4	
Using SES Feature Nodes	39
Overview	39
Example Control Plan - In-Roamer	39
Example Control Plan - Out-Roamer	40
Chapter 5	
Configuration	43
Overview	43
eserv.config Configuration	43
sesTrigger	44
macroNodes	55
dbCleanup	58
serviceLibrary	59
SLEE.cfg Configuration	60
acs.conf Configuration	60
Chapter 6	
Background Processes	61
Overview	61
dbCleanup	61

Statistics	61
Replication.....	62

Chapter 7

About Installation and Removal 67

Overview.....	67
Installation and Removal Overview.....	67

About This Document

Scope

The scope of this document includes all functionality a user must know in order to effectively install and operate the Subscriber Event Service application. It does not include detailed design of the service.

Audience

This guide is written primarily for Subscriber Event Service administrators. However, the overview sections of the document are useful to anyone requiring an introduction.

Prerequisites

A solid understanding of UNIX and a familiarity with IN concepts are an essential prerequisite for safely using the information contained in this technical guide. Attempting to install, remove, configure or otherwise alter the described system without the appropriate background skills, could cause damage to the system; including temporary or permanent incorrect operation, loss of service, and may render your system beyond recovery.

Although it is not a prerequisite to using this guide, familiarity with the target platform would be an advantage. See also the relevant standards, for example, Q713.

This manual describes system tasks that should only be carried out by suitably trained operators.

Related Documents

The following documents are related to this document:

- *Service Management System Technical Guide*
- *Control Plan Editor User's Guide*
- *Service Logic Execution Environment Technical Guide*

Document Conventions

Typographical Conventions

The following terms and typographical conventions are used in the Oracle Communications Network Charging and Control (NCC) documentation.

Formatting Convention	Type of Information
Special Bold	Items you must select, such as names of tabs. Names of database tables and fields.
<i>Italics</i>	Name of a document, chapter, topic or other publication. Emphasis within text.
Button	The name of a button to click or a key to press. Example: To close the window, either click Close , or press Esc .
Key+Key	Key combinations for which the user must press and hold down one key and then press another. Example: Ctrl+P or Alt+F4 .
Monospace	Examples of code or standard output.
Monospace Bold	Text that you must enter.
<i>variable</i>	Used to indicate variables or text that should be replaced with an actual value.
menu option > menu option >	Used to indicate the cascading menu option to be selected. Example: Operator Functions > Report Functions
hypertext link	Used to indicate a hypertext link.

Specialized terms and acronyms are defined in the glossary at the end of this guide.

System Overview

Overview

Introduction

This chapter explains what the Subscriber Event Service is and how it works.

In this chapter

This chapter contains the following topics.

Subscriber Event Service 1

Subscriber Event Service

Introduction


The Subscriber Event Service (SES) enables a service provider to send text messages to roaming subscribers (both their own and foreign subscribers) when they roam in and out of their network.

For example, a network operator may wish to greet all in-bound roamers with a "Welcome to our network", or "Thank you for using our network" message to all out-roaming subscribers.

Messages can be used to convey anything the network operator wants, for instance, advising of cheap rates at certain times of day.


In-Roaming diagram

This diagram shows the sequence of network activities that occur when a subscriber enters your network.




Out-Roaming diagram

This diagram shows the sequence of network activities that occur when a subscriber leaves your network.



Network diagram

This diagram shows how the NCC SLC receives notification that a subscriber is roaming.



Message rules

The messages can be configured as priority or non-priority. When selecting messages to send, all the priority messages are selected before any non-priority messages. The number of messages to select and send is configurable.

Messages can also be configured as general (they can be sent to any subscriber), or non-general (they can only be sent to specific subscribers, based on country code (MCC) and network code (MNC) of the subscriber).

Example scenarios

In this example the messages available have been configured as priority or non priority messages for country/ network code as follows:

Priority Messages	Country - network code	Non Priority Messages	Country - network code
Welcome from 123	123 - 98	Free texting	531 - 01
Welcome from 531	531 - 01	Cheap text day	any
Cut rate calls	123 - 98	Extra minutes	any
Flybys	any	Easy top up	any
Secure PIN	any	Cheaper text	any

Priority Messages	Country - network code
Outages	any
Upgrade deals	any

Non Priority Messages	Country - network code
Local weather	any

The inbound general messages set up using the **Inbound General Messages** (on page 21) tab are:

Priority Messages
Flybys
Secure PIN

Non Priority Messages
Cheap text day
Extra minutes

The inbound network specific messages set up using the **Inbound Messages** (on page 23) tab are:

Priority Messages
Welcome from 123
Welcome from 531

Non Priority Messages
Free texting

The outbound general messages set up using the **Outbound General Messages** (on page 25) tab are:

Priority Messages
Flybys
Secure PIN
Outages
Upgrade deals

Non Priority Messages
Easy top up
Cheaper text
Local weather

The outbound network specific messages set up using the **Outbound Messages** (on page 28) tab are:

Priority Messages
Cut rate calls

Non Priority Messages
Free texting

Note: The same messages can be used in any of the inbound/ outbound lists.


The maximum number of inbound messages has been configured at four.

The maximum number of outbound messages has been configured at five.

The days since contact is configured at two days.

Example in-roaming control plan

Here is the example in-roaming control plan used in scenarios 1 and 2.



For more information about:

- Control plans, see *CPE User's Guide*
- SES feature nodes, see *Feature Nodes Reference Guide*

Scenario 1

A roaming subscriber enters the network from a non specific country and network. The message selection in the control plan is based on latest available.

The following actions occur:

Step	Action
1	SES is triggered by the network.
2	The control plan using the In-Roamer Contact Check and In-Roamer Messages Selection feature nodes is executed.

Step	Action
3	If, within the configured two days, the subscriber: • Has been contacted, the 'Contacted' branch on the In-Roamer Contact Check feature node is taken and the subscriber gets no messages. • Has not been contacted, the 'Not Contacted' exit is taken.
4	Two lists of messages (priority and non priority) are created from the inbound general messages list, based on the maximum number of messages to be sent, specified in the In-Roamer Messages Selection feature node, and the priority assigned to the message. In this example the list consists of the messages: • Flybys (priority general message) • Secure PIN (priority general message) • Cheap text day (non priority message) • Extra minutes (non priority message).
5	The messages are sent to the subscriber.

Scenario 2


A roaming subscriber enters the network from country code 531 and network code 01. The message selection in the control plan is based on latest available.

The following actions occur:

Step	Action
1	SES is triggered by the network.
2	The control plan using the In-Roamer Contact Check and In-Roamer Messages Selection feature nodes is executed.
3	If, within the configured two days, the subscriber: • Has been contacted, the 'Contacted' branch on the In-Roamer Contact Check feature node is taken and the subscriber gets no messages. • Has not been contacted, the 'Not Contacted' exit is taken.
4	Two lists of messages (priority and non priority) are created from both the inbound messages and inbound general messages lists, based on the maximum number of messages to be sent, specified in the In-Roamer Messages Selection feature node, and the priority assigned to the message. In this example the list consists of the messages: • Welcome from 531 (priority specific 531 country message) • Flybys (priority general message) • Secure PIN (priority general message) • Free texting (non priority specific 531 country message)
5	The messages are sent to the subscriber.

Example out-roaming control plan

Here is the example control plan used in scenarios 3, 4, and 5.



For more information about:

- Control plans, see *CPE User's Guide*
- SES feature nodes, see *Feature Nodes Reference Guide*

Scenario 3

A roaming subscriber leaves the network to a specific country (531) and network (01). The message selection in the control plan is based on latest available.

The following actions occur:

Step	Action
1	SES is triggered by the network.

Step	Action
2	The control plan using the Out-Roamer Contact Check and Out-Roamer Messages Selection feature nodes is executed.
3	If the subscriber: • Has been contacted within the configured two days, the 'Contacted' branch on the Out-Roamer Contact Check feature node is taken and the subscriber gets no messages. • Has opted out, the 'Opted Out' exit is taken and the subscriber gets no messages. • Has not been contacted within the configured two days, the 'Not Contacted' exit is taken.
4	Two lists of messages (priority and non priority) are created from both the outbound messages and outbound general messages lists, based on the maximum number of messages to be sent, specified in the Out-Roamer Messages Selection feature node, and the priority assigned to the message. In this example the list consists of the messages: • Cut rate calls (priority specific 531 country message) • Flybys (priority general message) • Secure PIN (priority general message) • Outages (priority general message) • Upgrade deals (priority general message). Note: The message limit stops any of the general non priority messages being sent.
5	The messages are sent to the subscriber.

Scenario 4

A roaming subscriber leaves the network to a country and network not specified in SES. The message selection in the control plan is based on latest available.

The following actions occur:

Step	Action
1	SES is triggered by the network.
2	The control plan using the Out-Roamer Contact Check and Out-Roamer Messages Selection feature nodes is executed.
3	If the subscriber: • Has been contacted within the configured two days, the 'Contacted' branch on the Out-Roamer Contact Check feature node is taken and the subscriber gets no messages. • Has opted out, the 'Opted Out' exit is taken and the subscriber gets no messages. • Has not been contacted within the configured two days, the 'Not Contacted' exit is taken.
4	Two lists of messages (priority and non priority) are created from the outbound general messages list, based on the maximum number of messages to be sent, specified in the Out-Roamer Messages Selection feature node, and the priority assigned to the message. In this example the list consists of the messages: • Flybys (priority general message) • Secure PIN (priority general message) • Outages (priority general message)

Step	Action
	• Upgrade deals (priority general message) • Easy top up (non-priority general message to fulfill the message count).
5	The messages are sent to the subscriber.

Scenario 5


A roaming subscriber leaves the network to a specific country (531) and network (01). The message selection in the control plan is based on random.

The following actions occur:

Step	Action
1	SES is triggered by the network.
2	The control plan using the Out-Roamer Contact Check and Out-Roamer Messages Selection feature nodes is executed.
3	If the subscriber: • has been contacted within the configured two days, the 'Contacted' branch on the Out-Roamer Contact Check feature node is taken and the subscriber gets no messages. • Has opted out, the 'Opted Out' exit is taken and the subscriber gets no messages. • Has not been contacted within the configured two days, the 'Not Contacted' exit is taken.
4	Two lists of messages (priority and non priority) are created from both the outbound messages and outbound general messages lists, based on the maximum number of messages to be sent, specified in the Out-Roamer Messages Selection feature node, and the priority assigned to the message.
5	A selection is made randomly from the priority lists until the message count is reached or the list is exhausted. In this case a random selection creates a list like: • Cut rate calls (priority specific 531 country message) • Flybys (priority general message) • Secure PIN (priority general message) • Outages (priority general message) • Upgrade deals (priority general message) Note: The message limit for this example stops any of the non priority messages being sent.
6	A further selection is made randomly from the non priority lists until the message count is reached or the list is exhausted. In this example the final list could consist of messages: • Free texting (non priority specific 531 country message) • Easy top up (non priority general message) • Cheaper text (non priority general message) • Local weather (non priority general message)
7	The messages are sent to the subscriber.

Architectural diagram


Here is a diagram of the Subscriber Event Service architecture.



SES configuration diagram

This diagram shows the three configuration areas to fully enable SES.

Note: The Trigger Rules used depend on the contents of the `databaseLogin` parameter. If present and has a value, the SES trigger rules from the `eserv.config` are used, if missing or empty, the SES Configuration rules on the **Trigger Rules** (on page 30) tab are used.



Getting Started

Overview

Introduction

This chapter explains how to access the Subscriber Event Service configuration screens.

In this chapter

This chapter contains the following topics.

Accessing Subscriber Event Service Configuration 13

Accessing Subscriber Event Service Configuration

Accessing SMS

To access Service Management System, launch the application using the Webstart icon of the SMS machine that SES has been installed on.

For more information, see *SMS User's Guide*.

After a short while the login screen appears.

SMS Login screen

Here is an example of the SMS Login screen.

SMS Login

ORACLE®
COMMUNICATIONS
Network Charging and Control

User Name

Password

Copyright © 1998 - 2010 Oracle. All rights reserved.
 Oracle is a registered trademark of Oracle Corporation and/or its affiliates.
 Other names may be trademarks of their respective owners

OK Cancel

Logging into SMS


Follow these steps to log into SMS.

Step	Action
1	In the User Name field, type your username.
2	In the Password field, type your password.
	Notes: • Passwords are case sensitive. • You have three attempts to enter a correct username and password before the User ID is locked. If this happens, you must see your System Administrator to re-activate it.
3	Click OK .
	Result: You see the Service Management System main screen.

Accessing SES

Follow these steps to access the SES configuration screens.

Step	Action
1	Select the Services > SES Service menu options.




Result: You see the SES Configuration screen, defaulting to the **Trigger Rules** tab.

General screen information

The contents of screen records can be sorted by single clicking the column heading to sort by.

The status bar at the bottom of the screen shows update details for the row selected.

Example:



The screenshot shows a software window titled "SU - SES Configuration". At the top, there is a toolbar with buttons for "New...", "Edit...", "Delete...", "Refresh", "Close", and "Help". Below the toolbar is a tab labeled "Trigger Rules". The main area of the window contains a table with the following data:

Event Class	Event Type	Service Key	Country Code	Network C...	MSISDN	Enabled	Last Updated	By
CAMEL Mobili ...	Location Upd ...	9	531	001		✓	22/08/2012 03...	SU
CAMEL Mobili ...	Location Upd ...	9	123	98		✓	22/08/2012 03...	SU

SES Configuration Screens

Overview

Introduction

This chapter explains the functions of each SES configuration screen.

The topics are presented in the recommended sequence of configuration.

In this chapter

This chapter contains the following topics.

Messages	17
Inbound General Messages	21
Inbound Messages	23
Outbound General Messages	25
Outbound Messages	28
Trigger Rules	30
Contact History	36

Messages

Introduction


This tab enables you to configure all the messages available within SES, including their availability dates and whether they are priority or not. You must add messages using this tab first, so that they will be available on the other message tabs.

There are two types of messages that a handset roaming into or out of the network can receive:

- General messages: those that can be sent to any handset
- Messages: those that can be sent to country and network specific handsets

Messages tab

Here is an example of the **Messages** tab.



Messages tab columns

This table describes the content of each column.


Field	Description
Name	A user friendly message name.
Priority	Indicates if this message is priority or not priority. Note: Priority messages are always looked at first to fulfill the number to send parameter, see Inbound/Outbound Roaming Messages.
Active	When the message was (will be) available for selection.
Expiry	When the message was (will be) unavailable for selection.
Last Updated	Date and time stamp for the last update to this message.
By	Username of user that made the last update.

Note: The Activity, Expiry and Last Updated times are in relation to the time zone configured for SMS. (See *Service Management System Technical Guide*).

Adding new messages

Follow these steps to add new messages.

Step	Action
1	Select the Messages tab.

Step	Action
	Result: The current messages are listed.
2	Click New... Result: The New Message screen appears.
	
3	Enter a message Name . This name should be meaningful and descriptive for a user, for example "Free texting".
4	Select the Priority check box, if required, to make this a priority message. This means it will be selected before non-priority messages.
5	To: - Set an availability date and time for this message, select the Active check box. Result: The Wait until date and time boxes become available. Enter or select the relevant values. - Make the message available immediately, deselect the Active check box.
6	To: - Set an expiry date and time for this message, select the Expiry check box. Result: The Expires on date and time boxes become available. Enter or select the relevant values. - Make the message never expire, deselect the Expiry check box. It can be edited later if required.
7	Enter the text of the message that will be sent to a subscriber. Tip: The maximum message length is 120 ASCII characters.
	Result: The Save button becomes available.
8	Click Save .

Editing messages

Follow these steps to edit messages.

Step	Action
1	Select the Messages tab. Result: The current messages are listed.
2	In the table, select the message to edit.
3	Click Edit.... Result: The Edit Message screen appears.

- | | |
|---|---|
| 4 | Make the required changes to the fields, as described in <i>Adding new messages</i> (on page 18). |
| 5 | Click Save . |

Deleting messages

Follow these steps to delete messages.

Step	Action
1	Select the Messages tab. Result: The current messages are listed.
2	In the table, select the message to delete. Warning: You should only delete messages that have expired. Expired messages are automatically deleted by <i>dbCleanup</i> (on page 58) after a configured number of days.
3	Click Delete....

Step	Action
4	Result: The Delete Message confirmation screen appears. Click Delete.


Inbound General Messages

Introduction

This tab allows you to set up the available messages that can be sent to any subscriber inbound to the network, as against messages that are matched on country and network codes.

Inbound General Messages tab

Here is an example of the **Inbound General Messages** tab.




Inbound general messages tab columns

This table describes the content of each column.

Field	Description
Message	The message name.
Last Updated	Date and time stamp for the last update to this message (SMS time zone value).
By	Username of user that made the last update.


Adding new inbound general messages

Follow these steps to add new inbound general messages.

Step	Action
1	Select the Inbound General Messages tab. Result: The current inbound general messages are listed.
2	Click New.... Result: The New Inbound General Message screen appears.
	
3	Select the required Message from the drop down list. Tip: This is the list of messages maintained on the Messages <i>tab</i> (on page 17).
4	Click Save .

Editing inbound general messages

Follow these steps to change an existing inbound general message.

Step	Action
1	Select the Inbound General Messages tab. Result: The current inbound general messages are listed.
2	In the table, select the message to edit.
3	Click Edit.... Result: The Edit Inbound General Message screen appears.
	
4	Select the required Message from the drop down list.
5	Click Save .

Deleting inbound general messages

Follow these steps to delete inbound general messages.

Step	Action
1	Select the Inbound General Messages tab. Result: The current inbound general messages are listed.
2	In the table, select the message to delete.
3	Click Delete.... Result: The Delete Inbound General Message screen appears.
4	Click Delete .


Inbound Messages

Introduction

This tab allows you to set up the available messages that can be sent to a subscriber inbound to the network from a specific country and network, as against general messages that are not matched on country and network codes.

Inbound Messages tab

Here is an example of the **Inbound Messages** tab.




Inbound messages tab columns

This table describes the content of each column.

Field	Description
Country	The country code the subscriber has just roamed from.
Network	The network the subscriber has just roamed from.
Message	The message name.
Last Updated	Date and time stamp for the last update to this message (SMS time zone value).
By	Username of user that made the last update.


Adding new inbound messages

Follow these steps to add new inbound messages.

- | Step | Action |
|------|---|
| 1 | Select the Inbound Messages tab.
Result: The current inbound messages are listed. |
| 2 | Click New...
Result: The New Inbound Network Specific Message screen appears. |
| |  |
| 3 | Enter the Country Code (MCC) to associate with the message. |
| 4 | Enter the Network Code (MNC) to associate with the message.
Warning: You must input the code with the correct number of leading zeroes, for example 01 (2-digit MNC), or 123 (3 digit MNC)
Result: The Save button becomes available. |
| 5 | Select the Message to associate with the Country and Network Code from the drop down list.
Tip: This is the list of messages maintained on the Messages tab (on page 17). |
| 6 | Click Save . |
- Note:** For a list of MCC and MNC, refer to ITU E.212 ("Land Mobile Numbering Plan") documentation.

Editing inbound messages

Follow these steps to edit an existing inbound message.

Step	Action
1	Select the Inbound Messages tab. Result: The current inbound messages are listed.
2	In the table, select the Inbound Message to edit.
3	Click Edit... Result: The Edit Inbound Network Specific Message screen appears.
	
4	Make the required changes to the fields, as described in <i>Adding new inbound messages</i> (on page 24).
5	Click Save .

Deleting inbound messages

Follow these steps to delete inbound messages.

Step	Action
1	Select the Inbound Messages tab. Result: The current inbound messages are listed.
2	In the table, select the inbound message to delete.
3	Click Delete... Result: The Delete Inbound Network Specific Message confirmation screen appears.
4	Click Delete .


Outbound General Messages

Introduction

This tab lists the available messages that can be sent to any subscriber out bound from the network, as against messages that are matched on country and network codes.

Outbound General Messages tab

Here is an example of the **Outbound General Messages** tab.



Outbound general messages tab columns


This table describes the content of each column.

Field	Description
Message	The message name.
Last Updated	Date and time stamp for the last update to this message (SMS time zone value).
By	Username of user that made the last update.

Adding new outbound general messages


Follow these steps to add new outbound general messages.

Step	Action
1	Select the Outbound General Messages tab. Result: The current outbound general messages are listed.
2	Click New.... Result: The New Outbound General Message screen appears.

Step	Action
	
3	Select the Message from the drop down list. Tip: This is the list of messages maintained on the Messages tab (on page 17). The default is the first message in the list.
4	Click Save .

Editing outbound general messages

Follow these steps to change an outbound general message.

Step	Action
1	Select the Outbound General Messages tab. Result: The current outbound general messages are listed.
2	In the table, select the message you want to edit.
3	Click Edit... Result: The Edit Outbound General Message screen appears.
	
4	Select the Message from the drop down list.
5	Click Save .

Deleting outbound general messages

Follow these steps to delete outbound general messages.

Step	Action
1	Select the Outbound General Messages tab. Result: The current outbound general messages are listed.
2	In the table, select the general outbound message to delete.
3	Click Delete... Result: The Delete Outbound General Message confirmation screen appears.

Step	Action
4	Click Delete .


Outbound Messages

Introduction

This tab lists the available messages that can be sent to any subscriber out bound from the network to a specific country and network, as against general messages that are not matched on country and network codes.

Outbound Messages tab

Here is an example of the **Outbound Messages** tab.



Outbound messages tab columns

This table describes the content of each column.

Field	Description
Country	The country code the subscriber is roaming to.
Network	The network the subscriber is roaming to.
Message	The message name.
Last Updated	Date and time stamp for the last update to this message (SMS time zone value).
By	Username of user that made the last update.

Adding new outbound messages

Follow these steps to add new outbound messages.

Step	Action
1	Select the Outbound Messages tab. Result: The current outbound messages are listed.
2	Click New... Result: The New Outbound Network Specific Message screen appears.

3	Enter the Mobile Country Code (MCC) to associate with the message.
4	Enter the Mobile Network Code (MNC) to associate with the message. Result: The Save button becomes available.
5	Select the Message to associate with the Country and Network Code from the drop down list.

Tip: This is the list of messages maintained on the **Messages tab** (on page 17).


6	Click Save .
---	---------------------

Note: For a list of MCC and MNC, refer to ITU E.212 ("Land Mobile Numbering Plan") documentation.

Editing outbound messages

Follow these steps to edit an outbound message.

Step	Action
1	Select the Outbound Messages tab. Result: The current outbound messages are listed.
2	In the table, select the Outbound Message to edit.
3	Click Edit... Result: The Edit Outbound Network Specific Message screen appears.

Step	Action
	

- 4 Make the required changes to the fields, as described in *Adding new outbound messages* (on page 29).
- 5 Click **Save**.

Deleting outbound messages

Follow these steps to delete outbound messages.

Step	Action
1	Select the Outbound Messages tab. Result: The current outbound messages are listed.
2	In the table, select the outbound message to delete.
3	Click Delete.... Result: The Delete Outbound Network Specific Message confirmation screen appears.
4	Click Delete .

Trigger Rules

Introduction


This tab enables you to define the rules for what to trigger on receipt of MAP Mobility Notification messages. You can select control plans to be run which can send text messages. For example, sending welcome and farewell messages in response to IMSI attach and detach messages.

There are two sets of trigger rules that may be established. The rule set used depends on the contents of the `databaseLogin` parameter in the `sesTrigger` (on page 44) section of the `eserv.config` file. If the parameter is:

- Missing or empty, the **Trigger Rules** tab set is used
- Otherwise the rules in the configuration file are used

Trigger Rules tab

Here is an example of the **Trigger Rules** tab.



Trigger rules tab columns

This table describes the content of each column.

Field	Description
Event Class	The basic type of event. Currently just CAMEL Mobility Management is supported.
Event Type	The exact type of message.
Service Key	This is a parameter of the CAMEL Mobility Management event that allows different services to be treated differently.
Country Code	The MCC the subscriber is roaming to or from. Note: For a list of MCC, refer to ITU E.212 ("Land Mobile Numbering Plan") documentation.
Network Code	The home network (MNC) for the subscriber. The Country Code and Network Code are both used as prefixes in the IMSI and CAMEL Mobility Management events. These two codes identify the subscriber home network. Note: For a list of MNC, refer to ITU E.212 ("Land Mobile Numbering Plan") documentation.

Field	Description
MSISDN	Mobile Station ISDN number.
Enabled	This rule is active indicator (selected = active),
Last Updated	Date and time stamp for the last update to this message (SMS time zone value).
By	Username of user that made the last update.

Not visible on this tab, but required when adding or editing a trigger rule.

Field	Description
Service Provider	The telco providing the SES service/ACS customer.
Control Plan	The control plan to execute once a trigger match has occurred.

Adding new trigger rules

Follow these steps to add new trigger rules.

Step	Action
1	Select the Trigger Rules tab. Result: The Trigger Rules are listed.
2	Click New... Result: The New Trigger Rule screen appears. Tip: A blank field results in a match against everything for that field and is therefore optional.

Step	Action
New Trigger Rule Event Class: CAMEL Mobility Management Event Type: any Service Key: Country Code: Network Code: MSISDN: Enabled: ☒ Service Provider: Control Plan: Please press ENTER after keying service provider or control plan names. This will cause the value entered to be retrieved and validated. You can search in either field by entering partial names. Help Cancel Save	

3 Select the **Event Class** from the drop down.

Warning: This field is mandatory.

4 Select the **Event Type** from the drop down list.

Can be one of:

- Any
- Location update in the same VLR service area
- Location update to another VLR service area
- IMSI attach
- MS initiated IMSI detach (explicit detach)
- Network initiated IMSI detach (implicit detach)
- Subscriber Busy
- Subscriber Idle

Warning: This field is mandatory.

5 Enter the **Service Key** if required.

6 Enter the **Country Code** (MCC) if required.

Step	Action
7	Enter the Network Code (MNC) if required.
8	Enter the MSISDN if required.
9	Select the Enabled check box to make this trigger available.
10	Perform one of the following: • Select the Service Provider from the drop down list, or, if the list is blank • Enter the initial digits and press Enter to search and validate the entry. If you leave the field blank and press Enter the drop down list will be populated with all available Service Providers. Result: The Service Provider value is validated and selected as valid and the control plan drop down list is populated. Warning: This field is mandatory.
12	Perform one of the following: • Select the Control Plan from the drop down list • Enter the initial digits and press Enter to search and validate the entry Result: The control plan value is validated and ticked as valid, and the Save button becomes available. Warning: This field is mandatory.
13	Click Save .

Note: For a list of MCC and MNC, refer to ITU E.212 ("Land Mobile Numbering Plan") documentation.

Editing trigger rules

Follow these steps to edit trigger rules.

Step	Action
1	Select the Trigger Rules tab. Result: The Trigger Rules are listed.
2	In the table, select the Trigger Rule to edit.
3	Click Edit... Result: The Edit Trigger Rule screen appears.

Step	Action

- 3 Make the required changes to the fields, as described in *Adding new trigger rules* (on page 32).
- 4 Click **Save**.

Deleting trigger rules

Follow these steps to delete trigger rules.

Step	Action
1	Select the Trigger Rules tab. Result: The Trigger Rules are listed.
2	In the table, select the trigger rule to delete.
3	Click Delete.... Result: The Delete Trigger Rule confirmation screen appears.
4	Click Delete .

Contact History

Introduction

This tab enables you to view the roaming subscriber's history of messages sent. The available history is governed by the number of days history messages are kept in the database (defined in `dbCleanup` (on page 58) configuration).

The contact history is added to every time a message is successfully sent to an in-roaming or out-roaming subscriber. Population of history will be performed by an external application, for example, Deliver SM.

Contact History tab

Here is an example of the **Contact History** tab.

Tip: This tab is empty until a search for the contents is started. See *Viewing contact history* (on page 37).

The screenshot shows a software window titled "SU - SES Configuration". At the top, there are buttons for "New...", "Edit...", "Delete...", "Refresh", "Close", and "Help". Below these is a tab labeled "Contact History". Under the tab, there are two text input fields, one for "IMSI" and one for "MSISDN", followed by a "Search" button. Below the search area is a table with the following columns: "MSISDN", "IMSI", "Application", "Tag", "Timestamp", "Last Updated", and "By". The table is currently empty.

Contact tab columns

This table describes the contents of each column.

Field	Description
MSISDN	Mobile Station ISDN number.
IMSI	International Mobile Subscriber Identity.
Application	When present, configuration information from the application which populated the contact history, for example. Deliver SM feature node.

Field	Description
Tag	All messages sent are tagged by the sending feature node. These tags are internal, auto generated and informative only.
Timestamp	Time message sent to the subscriber (SMS time zone value).
Last Updated	Date message sent to the subscriber (SMS time zone value).
By	Username or application name that made the last update.

Viewing contact history

Follow these steps to view the contact history for a subscriber.

- | Step | Action |
|------|---|
| 1 | Select the Contact History tab.
Result: The contact history screen shows with unpopulated columns. |
| 2 | Type either the IMSI or the MSISDN (both is not allowed) of the subscriber to view the history of.
Tip: In either case, just the leading digits may be entered to broaden the search results.
Result: The Search button becomes available. |
| 3 | Click Search .
Result: The search results for the requested IMSI or MSISDN are displayed in the grid. |

SU - SES Configuration

New... Edit... Delete... Refresh Close Help

Trigger Rules Messages Inbound Messages

Inbound General Messages Outbound Messages Outbound General Messages Contact History


IMSI 3 Search

MSISDN

MSISDN	IMSI	Application	Tag	Timestamp	Last Updated	By
51089202	345554354	CPMapp	530:1	01/Jan/1970 00:0...	12/Apr/2006 02:3...	OPS\$SMF_OPER
51089202	345554354	CPMapp	530:1	12/Apr/2006 02:3...	12/Apr/2006 02:3...	OPS\$SMF_OPER
51089201	345554354		530:1	01/Jan/1970 00:0...	12/Apr/2006 00:5...	OPS\$SMF_OPER

(GUID 51089202-19700101000000-01) was written by OPS\$SMF_OPER on 12/Apr/2006 at 02:35:27 using terminal REPLIC

- 4 To view the actual message text, select the message row and click **Edit...**
Result: The message details are displayed.

Step	Action
5	 Click Close to exit.

Using SES Feature Nodes

Overview

Introduction

This chapter explains how SES uses ACS. This includes details on the SES specific feature nodes that are used in the ACS Control Plan Editor (CPE). These check subscribers on entering or leaving a network using SES and determine whether to send them messages and if so, determine the number of messages to be sent.

For an overview of ACS and the ACS Control Plan Editor, see the relevant ACS or CPE user's guides.

In this chapter

This chapter contains the following topics.

Example Control Plan - In-Roamer	39
Example Control Plan - Out-Roamer.....	40

Example Control Plan - In-Roamer

In-roaming control plan process


This example shows how the SES in-roaming feature nodes can be used in a control plan. For this example the In-Roamer Contact Check feature node has been configured at two days, and the In-Roamer Messages Selection feature node has been configured at two messages.

The following list of actions typify the sequence of in-roaming events.

- 1 A roaming subscriber enters the network and the network triggers SES.
- 2 The subscriber details match the configuration requirements from the Trigger Rules.
- 3 The example control plan is invoked.
- 4 The In-Roamer Contact Check (sesInRCC) feature node determines if this subscriber has been sent messages within the contact period of 2 days.
- 5 If there has been contact within the contact period, the control plan exits.
- 6 The In-Roamer Messages Selection (sesInRMS) feature node checks for messages (up to the configured total) to send.
- 7 If there were no messages found to send, the control plan exits.
- 8 A node that sends short messages (Notification) attempts to send the messages.

In-roaming control plan

Here is an example in-roaming control plan.



Example Control Plan - Out-Roamer

Out-roaming control plan process

This example shows how the out-roaming feature nodes can be used in a control plan. For this example the Out-Roamer Contact Check feature node has been configured at two days, and the Out-Roamer Messages Selection node has been configured at two messages.


The following list of actions typify the sequence of out-roaming events.

- 1 A roaming subscriber leaves the network and the network triggers SES.
- 2 The subscriber details match the configuration requirements from the Trigger Rules.
- 3 The example control plan is invoked.
- 4 The Out-Roamer Contact Check feature node determines if this subscriber has been sent messages within the contact period of 2 days (sesOutRCC).

- 5 If the subscriber has opted out of receiving messages, the control plan exits (this could be other control plan features) (End).
- 6 If there has been contact within the contact period, the control plan exits (this could be other control plan features) (End).
- 7 The Out-Roamer Messages Selection feature node (sesOutRMS) checks for messages (up to the configured total) to send.
- 8 If there were no messages found to send, the control plan exits (this could be other control plan features) (End).
- 9 A feature node that sends short messages (Notification) attempts to send the messages (followed by other control plan features).

Out-roaming control plan

Here is an example out-roaming control plan.



Configuration

Overview

Introduction

This chapter explains the Subscriber Event Service configuration requirements.

In this chapter

This chapter contains the following topics.

eserv.config Configuration	43
sesTrigger	44
macroNodes	55
dbCleanup	58
serviceLibrary	59
SLEE.cfg Configuration	60
acs.conf Configuration	60

eserv.config Configuration

Introduction

The **eserv.config** file is a shared configuration file, from which many Oracle Communications Network Charging and Control (NCC) applications read their configuration. Each NCC machine (SMS, SLC, and VWS) has its own version of this configuration file, containing configuration relevant to that machine. The **eserv.config** file contains different sections; each application reads the sections of the file that contains data relevant to it.

The **eserv.config** file is located in the `/IN/service_packages/` directory.

The **eserv.config** file format uses hierarchical groupings, and most applications make use of this to divide the options into logical groupings.

Configuration File Format

To organize the configuration data within the **eserv.config** file, some sections are nested within other sections. Configuration details are opened and closed using either `{ }` or `[ ]`.

- Groups of parameters are enclosed with curly brackets – `{ }`
- An array of parameters is enclosed in square brackets – `[ ]`
- Comments are prefaced with a `#` at the beginning of the line

To list things within a group or an array, elements must be separated by at least one comma or at least one line break. Any of the following formats can be used, as in this example:

```
{ name="route6", id = 3, prefixes = [ "00000148", "0000473" ] }
{ name="route7", id = 4, prefixes = [ "000001049" ] }
```

or

```
{ name="route6"
```

```

        id = 3
        prefixes = [
            "00000148"
            "0000473"
        ]
    }
    { name="route7"
      id = 4
      prefixes = [
          "000001049"
      ]
    }
}

```

or

```

{ name="route6"
  id = 3
  prefixes = [ "00000148", "0000473" ]
}
{ name="route7", id = 4
  prefixes = [ "000001049" ]
}

```

eserv.config Files Delivered

Most applications come with an example **eserv.config** configuration in a file called **eserv.config.example** in the root of the application directory, for example, `/IN/service_packages/eserv.config.example`.

Editing the File

Open the configuration file on your system using a standard text editor. Do not use text editors, such as Microsoft Word, that attach control characters. These can be, for example, Microsoft DOS or Windows line termination characters (for example, ^M), which are not visible to the user, at the end of each row. This causes file errors when the application tries to read the configuration file.

Always keep a backup of your file before making any changes to it. This ensures you have a working copy to which you can return.

Loading eserv.config Changes

If you change the configuration file, you must restart the appropriate parts of the service to enable the new options to take effect.

Restarting

The following processes are restarted after configuration changes as indicated.

Process	Restart Action
sesTrigger	Sighup of sesTrigger or restart of the SLEE.
macronodes	Sighup of slee_acs or restart of the SLEE.

sesTrigger

sesTrigger configuration

Here is a high level view of the Subscriber Event Service (SES) trigger section of the **eserv.config**.

```

SES = {
    sesTrigger = {

```

```

maxOutstanding = 0
databaseLogin = "SCP/SCP"
reloadInterval = 600
pollTime = 20000
adapters = {
    xml_subscriber = {
        library = "libeaxXmlSubscriber.so"
        rejectLevel = 300
        rejectLevelReportPeriod = 6
        performanceReportPeriod = 10

        function = "sesLoadAdapter"
        timeout = 5
        called_party_noa = 0
        serviceKey = 120
        balance_service_key = 130 #
        redeem_service_key = 422 #
        balance_type_index = -1 # old value 0
        balance_amount_index = -1

        redeem_type_index = -1
        redeem_amount_index = 0
        faked_call_party = "0"
        listen_port = 1888
        connection_timeout = 60
        #remote_hosts = [ "10.21.120.235" ]
        log = true

# getSubscriberBalance
        balance_fields = [
            {
                name = "Active End" # the XML field name
                type = "date"
                announcementId = 2
                # >= 0 = variable part ID
                # the position of the value in the INAP Play
                Announcement
                # < 0 = use variable announcement ID
                required = false
                # required means the parameter is required to produce the
                XML response
                # if the parameter is missing the XML message will fail
            }
            {
                name = "Grace End"
                type = "date"
                announcementId = 3
                # >= 0 = variable part ID
                # the position of the value in the INAP Play
                Announcement
                # < 0 = use variable announcement ID
                required = false
                # if true and can not extract value the xml request will
                be failed
            }
        ]

# VoucherRedeem
        redeem_fields = [
            {
                name = "New Balance" # the XML field name
                type = "int"
                announcementId = 1

```

```

        # >= 0 = variable part ID
        # the position of the value in the INAP Play Announcement
        # < 0 = use variable announcement ID
        required = false
        # if true and can not extract value the xml request will be
failed
    }
    {
        name = "Active End" # the XML field name
        type = "date"
        announcementId = 2
        # >= 0 = variable part ID
        # the position of the value in the INAP Play Announcement
        # < 0 = use variable announcement ID
        required = false
        # if true and can not extract value the xml request will be
failed
    }
    {
        name = "Grace End"
        type = "date"
        announcementId = 3
        # >= 0 = variable part ID
        # the position of the value in the INAP Play Announcement
        # < 0 = use variable announcement ID
        required = false
        # if true and can not extract value the xml request will be
failed
    }
}
}# End of xml_subscriber
}# End of adapters
} # End of sesTrigger section.
} # End of SES section.

```

sesTrigger parameters

SES trigger application accepts the following trigger parameters.

adapters

Syntax: `adapters = {adapter1_name}{adapter2_name}`

Description: The adapters section specifies the adapter(s) required for SES to work.

Type: String

Optionality: Mandatory.

Allowed: Must be the default string.

Default:

- notemm, and/or
- xml_subscriber

Notes: See the relevant adapter parameter lists below.

Example:

```

adapters = {
    notemm = {
        library = "libseseNoteMM.so"
        function = "sesLoadAdapter"
        timeout = 5
        serviceKey = 120
    }
}
{
    xml_subscriber = {
        library = "libeaxXmlSubscriber.so"
    }
}

```

```

        function = "sesLoadAdapter"
        timeout = 5
        serviceKey = 511
        balance_service_key = 511
        voucher_service_key = 512
        balance_type_index = 0
        balance_amount_index = 1
        redeem_type_index = 0
        redeem_amount_index = 1
        faked_call_party = "0"
        listen_port = 8088
        remote_hosts = [ "host1.xyz.com", "host2.xyz.com" ]
        connection_timeout = 60
        log = true
    }
}

```

databaseLogin

Syntax: databaseLogin = <"user/password">
Description: Identifies where to get the trigger rules from.
Type: String
Optionality: Optional; if missing the default is used.
Allowed: Any valid user and password combination string.
Default: "SCP/SCP"
Notes: Setting databaseLogin to empty means use the trigger rules below instead of loading them from the database.
Example: databaseLogin = ""

maxOutstanding

Syntax: maxOutstanding = num
Description: Maximum number of transactions to ACS that may be outstanding at any time.
Type: Integer
Optionality: Optional; if missing the default is used.
Allowed: Any positive decimal integer, including 0.
Default: 0
Notes: 0 means no limit. If this limit is reached, any new requests will be rejected.
Example: maxOutstanding = 0

pollTime

Syntax: pollTime = msec
Description: PollTime for TCP/IP sockets in micro-seconds.
Type: Integer
Optionality: Optional, if missing the default is used.
Allowed: Any positive decimal integer
Default: 100000 (micro seconds)
Notes:
Example: pollTime = 20000

reloadInterval

Syntax:	<code>reloadInterval = <i>seconds</i></code>
Description:	How often to reload configuration (including database), in seconds.
Type:	Integer
Optionality:	Optional; if missing the default is used.
Allowed:	Any positive decimal integer, including 0.
Default:	0
Notes:	0 means never. In any case, we always reload on getting a SIGHUP.
Example:	<code>reloadInterval = 0</code>

notemm adapter parameters

These are the configuration parameters specific to the notemm adapter.

function

Syntax:	<code>function = "<i>name</i>"</code>
Description:	The entry point to this shared library.
Type:	string
Optionality:	Mandatory
Allowed:	Must be "sesLoadAdapter"
Example:	<code>function = "sesLoadAdapter"</code>

library

Syntax:	<code>library = "<i>name</i>"</code>
Description:	The shared library to load.
Type:	String
Optionality:	Mandatory
Allowed:	Any valid library name.
Default:	<code>"libeaxXmlSubscriber.so"</code>
Notes:	
Example:	<code>library = "libeaxXmlSubscriber.so"</code>

serviceKey

Syntax:	<code>serviceKey = <i>skey</i></code>
Description:	Service key for this adapter. This is the serviceKey used for triggering to ACS.
Type:	Integer
Optionality:	Optional; if missing the default is used.
Allowed:	Any valid service key.
Default:	511
Notes:	
Example:	<code>serviceKey = 511</code>

timeout

Syntax:	<code>timeout = <i>seconds</i></code>
Description:	Timeout, in seconds, on transactions.
Type:	Positive integer

Optionality:	Mandatory
Allowed:	Any positive number, including 0
Default:	0
Note:	0 means no timeout. This timeout should be set to a higher than a retry timeout parameter, if it exists, of any node, used in conjunction with this service, that sends a short message. This will prevent SES trigger from timing out before all messages are successfully sent.
Example:	<code>timeout = 5</code>

xml_subscriber adapter parameters

These are the configuration parameters specific to the xml_subscriber adapter.

balance_amount_index

Syntax:	<code>balance_amount_index = value</code>
Description:	Where to extract subscriber amount information from the PlayAnnouncement.
Type:	Integer
Optionality:	Optional (default used if not set).
Allowed:	-1 means to use the fixed announcements 0 or greater is the (0-based) index
Default:	1
Notes:	
Example:	<code>balance_amount_index = 1</code>

balance_service_key

Syntax:	<code>balance_service_key = skey</code>
Description:	The service key for get-balance triggering to ACS.
Type:	Integer
Optionality:	Optional (default used if not set).
Allowed:	Any valid service key.
Default:	511
Notes:	
Example:	<code>balance_service_key = 511</code>

balance_type_index

Syntax:	<code>balance_type_index = value</code>
Description:	Where to extract subscriber balance unit information from the PlayAnnouncement.
Type:	Integer
Optionality:	Optional (default used if not set).
Allowed:	-1 means to use the fixed announcements 0 or greater is the (0-based) index
Default:	0
Notes:	
Example:	<code>balance_type_index = 0</code>

`called_party_noa`

Syntax:	<code>called_party_noa = noa</code>
Description:	The called party nature of address configured.
Type:	Integer
Optionality:	Optional (default used if not set).
Allowed:	
Default:	0
Notes:	
Example:	<code>called_party_noa = 0</code>

`connection_timeout`

Syntax:	<code>connection_timeout = seconds</code>
Description:	Idle timeout on HTTP connections, in seconds.
Type:	Integer
Optionality:	Optional (default used if not set).
Allowed:	• 0 means no timeout • Any positive integer
Default:	0
Notes:	
Example:	<code>connection_timeout = 60</code>

`faked_call_party`

Syntax:	<code>faked_call_party = "value"</code>
Description:	Number to add to the IDP as "called party", seeing as how we don't have one. Some service loaders need this.
Type:	Numerical string
Optionality:	Mandatory
Allowed:	
Default:	"0"
Notes:	
Example:	<code>faked_call_party = "0"</code>

`function`

Syntax:	<code>function = "name"</code>
Description:	The entry point to this shared library.
Type:	string
Optionality:	Mandatory
Allowed:	Must be "sesLoadAdapter"
Example:	<code>function = "sesLoadAdapter"</code>

`library`

Syntax:	<code>library = "name"</code>
Description:	The shared library to load.
Type:	String

Optionality: Mandatory
Allowed: Any valid library name.
Default: No default
Notes:
Example: `library = "libeaxXmlSubscriber.so"`

`listen_port`

Syntax: `listen_port = port`
Description: Port to listen on.
Type: Integer
Optionality: Optional (default used if not set).
Allowed: Any valid port number.
Default: 8088
Notes:
Example: `listen_port = 8088`

`log`

Syntax: `log = true|false`
Description: Whether or not to log individual requests.
Type: Integer
Optionality: Mandatory
Allowed: true, false
Default: true
Notes:
Example: `log = true`

`performanceReportPeriod`

Syntax: `performanceReportPeriod = seconds`
Description: Defines the period (in seconds) after which a performance report will be generated.
Type: Integer
Optionality: Optional (default used if not set).
Allowed:
Default: 0 - no report will be generated
Notes:

- The reporting time is aligned with the system clock, NOT the application start time.
- The first performance report after SLEE startup may differ to that which is configured for the `performanceReportPeriod`, depending on when the SLEE was started within the clock aligned performance period.

Example: `performanceReportPeriod = 10`

`redeem_amount_index`

Syntax: `redeem_amount_index = value`
Description: Where to extract voucher redeem unit information from the PlayAnnouncement.
Type: Integer

Optionality: Optional (default used if not set).
Allowed: Any positive decimal integer, including 0.
Default: 1
Notes:
Example: `redeem_amount_index = 1`

`redeem_type_index`

Syntax: `redeem_type_index = value`
Description: Where to extract voucher redeem unit information from the PlayAnnouncement.
Type: Integer
Optionality: Optional, if missing the default is used.
Allowed: Any positive decimal integer, including 0.
Default: 0
Notes:
Example: `redeem_type_index = 0`

`rejectLevel`

Syntax: `rejectLevel = num`
Description: Determines the maximum number of new connections allowed per second. sesTrigger rejects any new connection that comes in over and above what is configured.
Type: Integer
Optionality: Optional (default used if not set).
Allowed:
Default: 0 - no traffic limit
Notes: Any negative number is treated as 0, that is, no limit set.
Example: `rejectLevel = 300`

`rejectLevelReportPeriod`

Syntax: `rejectLevelReportPeriod = seconds`
Description: Defines the period (in seconds) after which a reject report will be generated.
Type: Integer
Optionality: Optional (default used if not set).
Allowed:
Default: 0 - no report will be generated
Notes:

- The reporting time is aligned with the system clock, NOT the application start time.
- The first performance report after SLEE startup may differ to that which is configured for the rejectLevelReportPeriod, depending on when the SLEE was started within the clock aligned performance period.

Example: `rejectLevelReportPeriod = 10`

`remote_hosts`

Syntax: `remote_hosts = ["host1", "host2", ..., "hostn"]`
Description: List of remote hosts to allow connections from.
Type: Array of strings

Optionality: Optional (default used if not set).
Allowed: Any valid host names.
Default: [] (empty)
Notes: Empty means to allow connections from any hosts.
Example: `remote_hosts = [ "host1.xyz.com", "host2.xyz.com" ]`

`serviceKey`

Syntax: `serviceKey = skey`
Description: Service key for this adapter. This is the serviceKey used for triggering to ACS.
Type: Integer
Optionality: Optional; if missing the default is used.
Allowed: Any valid service key.
Default: 511
Notes:
Example: `serviceKey = 511`

`timeout`

Syntax: `timeout = seconds`
Description: Timeout, in seconds, on transactions.
Type: Positive integer
Optionality: Mandatory
Allowed: Any positive number, including 0
Default: 0
Note: 0 means no timeout.
 This timeout should be set to a higher than a retry timeout parameter, if it exists, of any node, used in conjunction with this service, that sends a short message. This will prevent SES trigger from timing out before all messages are successfully sent.
Example: `timeout = 5`

`voucher_service_key`

Syntax: `voucher_service_key = skey`
Description: The service key for voucher-redeem triggering to ACS.
Type: Integer
Optionality: Optional (default used if not set).
Allowed: Any valid service key.
Default: 512
Notes:
Example: `voucher_service_key = 512`

rules parameters

The trigger rules provide match information in order to determine the control plan to use.

Matching is done on:

- `event_class`, and

- event_type, then if needed
- msisdn (treated as a prefix).

SES trigger application accepts the following rules parameters.

Note: The rules config is only used if databaseLogin is present and empty above; otherwise the database is used.

enabled

Syntax: `enabled = true|false`
Description:
Type: Boolean
Optionality: Mandatory
Allowed: true, false
Default: none
Notes:
Example: `enabled = true`

event_class

Syntax: `event_class = class`
Description: The event class to match against for control plan triggering.
Type: Integer
Optionality: Mandatory
Allowed: Any valid event class.
Default: none
Notes: Used in conjunction with event_type and msisdn.
Example: `event_class = 4`

event_type

Syntax: `event_type = type`
Description: The event type to match against for control plan triggering.
Type: Integer
Optionality: Mandatory
Allowed:

- 1 (subscriber balance)
- 2 (voucher redeem)

Default: none
Notes: Used in conjunction with event_class and msisdn
Example: `event_type = 1`

msisdn

Syntax: `msisdn = value`
Description: The subscriber key to match against for control plan triggering.
Type: Integer
Optionality: Optional
Allowed: Any valid subscriber number or part number representing the start or number prefix of the subscriber.
Default: none

Notes: Used in conjunction with the `event_class` and `event_type` parameters when there are different triggers required that are based on subscriber number.

Example: `msisdn = "1234"`

`pin`

Syntax: `pin = "value"`

Description: Override for the generated PIN, if wanted.

Type: string

Optionality: Optional

Allowed:

Default: none

Notes: This is only used with the SES service loader.

Example: `pin = "xmlsubbal"`

`plan`

Syntax: `plan = "name"`

Description: The control plan to trigger to if the event class, event type and (when used) the `msisdn` are matched against.

Type: String

Optionality: Mandatory

Allowed: Any valid control plan name.

Default: none

Notes: The control plan must have already been cleanly compiled and saved.
This is only used with the SES service loader.

Example: `plan = "LEralph"`

`provider`

Syntax: `provider = "id"`

Description: The ID of the service provider.

Type: String

Optionality: Mandatory

Allowed: Any valid service provider ID.

Default: none

Notes: This is only used with the SES service loader.

Example: `provider = "su"`

macroNodes

macroNodes configuration

Here is an example of the Subscriber Event Service `SES.macroNodes` section of the `eserv.config`.

```
SES = {
  macroNodes = {
    outRoamerContactCheck = {
      optOutProfile = {
```

```

        block = 8
        tag = 0x500050
    }
}
inRoamerMessagesSelection = {
    generalMessageCache = {
        flushPeriodSeconds = 300
    }
}
outRoamerMessagesSelection = {
    generalMessageCache = {
        flushPeriodSeconds = 300
    }
}
} # end of macroNodes
}

```

macroNodes parameters

`macroNodes` accepts the following parameters.

outRoamerContactCheck parameters

The contact check parameters are held within the `optOutProfile` parameter set. There can be as many `optOutProfile` parameter sets as required. Any out-roamer subscribers matching this parameter will be ne sent any messages.

`block`

Syntax:	<code>block = value</code>
Description:	The profile block to use. This is where the flag is stored.
Type:	Integer
Optionality:	Mandatory
Allowed:	Numbers 1 to 16 depending on which of the following is required. 1 VPN Network 2 VPN Station 3 Customer 4 Call Plan 5 Global 6 CLI Subscriber 7 Service Number 8 Application Specific 1/CCS Account Reference 9 Application Specific 2 10 Application Specific 3 11 Application Specific 4 12 Application Specific 5 13 Application Specific 6 14 Application Specific 7 15 Application Specific 8 16 Any Valid
Default:	8
Notes:	For a full description of profile blocks, refer to <i>CPE User's Guide</i> .
Example:	<code>block = 8</code>

tag

Syntax:	<code>tag = value</code>
Description:	The tag in this profile where the opted out flag is stored.
Type:	Hex value
Optionality:	Mandatory
Allowed:	Hex value of any valid tag.
Default:	0x500050
Notes:	This should be the same one as used by the PI for your installation. For a full description of profile tags, refer to the <i>CPE User's Guide</i> .
Example:	<code>tag = 0x500050</code>

inRoamerMessagesSelection parameters

This parameter signals how often to update the in-roamer messages cache.

flushPeriodSeconds

Syntax:	<code>flushPeriodSeconds = seconds</code>
Description:	How often to reload the general message cache.
Type:	Integer
Optionality:	Mandatory
Allowed:	
Default:	300
Notes:	
Example:	<code>flushPeriodSeconds = 300</code>

generalMessageCache

Syntax:	<code>generalMessageCache = {parameter}</code>
Description:	The general message cache parameters.
Type:	List of parameters.
Optionality:	Mandatory
Allowed:	
Default:	
Notes:	
Example:	<code>generalMessageCache = { flushPeriodseconds = 300 }</code>

outRoamerMessagesSelection parameters

This parameter signals how often to update the out-roamer messages cache.

flushPeriodSeconds

Syntax:	<code>flushPeriodSeconds = seconds</code>
Description:	How often to reload the general message cache.
Type:	Integer
Optionality:	Mandatory
Allowed:	

Default: 300
Notes:
Example: `flushPeriodSeconds = 300`

generalMessageCache

Syntax: `generalMessageCache = {parameter}`
Description: The general message cache parameters.
Type: List of parameters.
Optionality: Mandatory
Allowed:
Default:
Notes:
Example:

```
generalMessageCache = {
    flushPeriodseconds = 300
}
```

dbCleanup

Introduction

dbCleanup removes messages and old contact information from the database on a regular basis. Refer to *dbCleanup* (on page 61) for more information. The frequency is provided through these parameters.

dbCleanup configuration

Here is an example of the Subscriber Event Service `SES.dbCleanup` section of the `eserv.config`.

```
SES = {
  dbCleanup = {
    user = "ses_admin"
    password = "ses_admin"
    hour = 0
    contactHistoryDays = 7
    messagesDays = 10
  } # end of dbCleanup
}
```

dbCleanup parameters

dbCleanup accepts the following parameters.

contactHistoryDays

How long to keep SES contact history information for after the text message is sent.

Default: 7
Allowed: Integer number of days.
Note: This parameter is mandatory.

hour

The hour in which to run the clean up.

- Default:** 0
- Allowed:** 0 to 23 to indicate what hour to start in, for example:
- 0 for between midnight and 1am
 - 14 for between 2pm and 3pm
- Note:** This parameter is mandatory.

messagesDays

How long to keep SES messages after they have expired.

- Default:** 10
- Allowed:** Integer number of days.
- Note:** This parameter is mandatory.

password

The password of the authorized user.

- Default:** ses_admin
- Allowed:** ses_admin
- Note:** This parameter is mandatory.

user

The authorized identification that can perform the removal activities.

- Default:** ses_admin
- Allowed:** ses_admin
- Note:** This parameter is mandatory.

serviceLibrary

serviceLibrary configuration

Here is an example of the Subscriber Event Service `SES.serviceLibrary` section of the `eserv.config`.

```
SES = {
    serviceLibrary = {
        loadAccountReferenceProfile = true
    }
}
```

serviceLibrary parameters

`serviceLibrary` accepts the following parameter.

loadAccountReferenceProfile

Whether to load the profile from the `CCS_ACCT_REFERENCE` table, based on the MSISDN.

- Default:** true
- Allowed:** true, false
- Note:** Optional

SLEE.cfg Configuration

Lines inserted

The installation of SES inserts the following lines into the installed **SLEE.cfg** file.

```
INTERFACE=sesIf sesTrigger.sh /IN/service_packages/SES/bin EVENT # Added by sesScp
SERVICEKEY=INTEGER 1111 sesIf # Added by sesScp    <<< servicekey for the sesTrigger
SERVICEKEY=INTEGER 1121 SES # Added by sesScp    <<< servicekey for talking to the SES service
loaded by slee_acs
SERVICE=SES 1 slee_acs SES # Added by sesScp    <<< defining the SES service in slee_acs
```

Note: The SERVICEKEY lines will need to be modified on most sites.

acs.conf Configuration

Lines inserted

The installation of SES inserts the following lines into the installed **acs.conf** file.

```
MacroNodePluginFile libsesMacroNodes.so    # Added by sesScp
ServiceEntry (SES,libsesService.so)        # Added by sesScp
```

Background Processes

Overview

Introduction

This chapter explains the SES background processes.

In this chapter

This chapter contains the following topics.

dbCleanup	61
Statistics	61
Replication	62

dbCleanup

Introduction

This SMS process is responsible for cleaning up the contact history so that it does not get too big.

The amount of contact history it keeps is configurable. See *dbCleanup* (on page 58) for details.

It is run from the inittab on non-clustered machines and it is a cluster service on clustered SMSs.

Stopping and starting the process

Enter the following commands to stop the process:

1. `cd /opt/ESERVsesDbCleanup/util`
2. `./stopsesDbCleanup -h logical_hostname`
3. `scstat | grep sesDbCleanup-harg`
No records should be returned.

Statistics

Introduction

An existing statistics system provides functions for the collection of basic statistical events. This is provided in the NCC SMS application and provisioned at installation. Statistics can be viewed using the SMS application (**Operator Functions > Stats Viewer** menu options), see *Service Management System Technical Guide*.

Below are tables describing each statistic type and event type.

Statistic types collected

The following statistic types are available for collection. Each statistic event (see *statistic events collected* below) has these six statistics collected.

Statistic Type	Description
<i>statistic_event_FAILED</i>	Triggered to ACS and received a failure response.
<i>statistic_event_REJECTED</i>	Did not successfully trigger to ACS.
<i>statistic_event_SUCCESS</i>	Triggered to ACS and received a success response.
<i>statistic_event_THROTTLED</i>	Rejected due to too many outstanding transactions.
<i>statistic_event_TIMEOUT</i>	Triggered to ACS and never heard back.
<i>statistic_event_TOTAL</i>	Total of all the above events.

Statistic events collected

The following statistic events are available for collection.

Note: Each of these events can have up to six statistics collected.

Statistic Event	Description
NOTE_MM_LOC_UP_SAME_VLR_StatisticType	Location update in the same VLR service area.
NOTE_MM_LOC_UP_OTHER_VLR_StatisticType	Location update to another VLR service area.
NOTE_MM_IMSI_ATTACH_StatisticType	IMSI attach.
NOTE_MM_MS_IMSI_DETACH_StatisticType	MS initiated IMSI detach (explicit detach).
NOTE_MM_NET_IMSI_DETACH_StatisticType	Network initiated IMSI detach (implicit detach).
NOTE_MM_ROUTE_UP_SAME_SGSN_StatisticType	Routing area update in the same SGSN service area.
NOTE_MM_SGSN_UP_NEW_SGSN_StatisticType	Routing area update to another SGSN service area.
NOTE_MM_SGSN_DISCONNECT_StatisticType	Routing area update to other SGSN disconnect by detach.
NOTE_MM_GPRS_ATTACH_StatisticType	GPRS attach.
NOTE_MM_MS_GPRS_DETACH_StatisticType	MS initiated GPRS detach.
NOTE_MM_NET_GPRS_DETACH_StatisticType	Network initiated GPRS detach.
NOTE_MM_NET_XFER_MS_UNREACH_StatisticType	Network initiated transfer to the "not reachable for paging" state.

Examples:

```
NOTE_MM_LOC_UP_SAME_VLR_FAILED
NOTE_MM_LOC_UP_SAME_VLR_REJECTED
NOTE_MM_LOC_UP_SAME_VLR_SUCCESS
```

Replication


Introduction

This topic explains the replication system used for SES. Replication is the system which transfers data between nodes in the IN installation.

Replicating SES tables


Follow these steps to replicate the SES tables.

Step	Action
1	Select the Operator Functions > Node Management menu options from the Service Management System main screen.




- Result:** The Node Management screen opens.
- 2 Select the **Table Replication** tab.
- Result:** The top level table types are shown.
- 3 Scroll down the left hand panel until the `Ses_Service` type is in view.
- 4 Expand the `Ses_Service` type.
- Result:** The tables for replication are shown.

Step	Action
------	--------




- 5 Select and drag each of the SES Service tables you wish to replicate from the left panel to each of the configured SLC nodes in the Allocated Replication Groups panel.

Example:

Tip: You must select SES_MESSAGE, before you can select the other message tables.

- 6 Click **Save**.

Result: The replication is saved and the Save Complete confirmation displays.

Step	Action
	 A screenshot of a 'Save Complete' dialog box. The title bar says 'Save Complete' with a close button. The text inside says 'Replication configuration saved. To activate it you must create the configuration file'. There is an 'OK' button at the bottom.
7	Click OK .
8	Click Create Config File . Result: A new config file is created and pushed out to the relevant nodes enabling the replicated tables to be used, and the confirmation is displayed.  A screenshot of a 'Replication Configuration' dialog box. The title bar says 'Replication Confi...' with a close button. The text inside says 'File Generated and Copied OK'. There is an 'OK' button at the bottom.
9	Click OK .
10	Click Close .

Note: For more information on replication, refer to *Service Management System Technical Guide*.

About Installation and Removal

Overview

Introduction

This chapter provides information about the installed components for the Oracle Communications Network Charging and Control (NCC) application described in this guide. It also lists the files installed by the application that you can check for, to ensure that the application installed successfully.

In this Chapter

This chapter contains the following topics.

Installation and Removal Overview 67

Installation and Removal Overview

Introduction

For information about the following requirements and tasks, see *Installation Guide*:

- NCC system requirements
- Pre-installation tasks
- Installing and removing NCC packages

SES packages

An installation of Subscriber Event Service includes the following packages, on the:

- SMS:
 - sesSms
 - sesCluster (for clustered SMS)
- SLC:
 - sesScp