# Oracle® Communications Network Charging and Control

**Provisioning Interface Alarms Guide** 





## Copyright

Copyright © 2023, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle, Java, and MySQL are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

# **Contents**

Alarm Topic Description	
PImanager	
Plprocess	
Plbatch	
Plbatch XML	

# **Alarm Topic Description**

#### **Alarm Generation**

Alarms on each configured node are written to the syslog and are then captured by the smsAlarmDaemon for entry in the SMF database.

For management of these alarms, see Service Management System Technical Guide.

### **Severity Levels**

This table describes the alarm severity levels.

Level	Abbreviation	Description
Critical	С	These alarms are raised when the application has encountered an error indicating that the system is unable to function.
Error	Е	These alarms indicate the application has encountered a serious problem completing a necessary task and could not complete the task.
Warning	W	Warnings are raised to indicate the application encountered a problem completing a non-mission critical task.
Notice	N	Notices are raised to indicate that the application has completed a task successfully.

#### **Alarm Format**

#### Alarms usually follow this format:

Mon DD 24:MM:SS hostname process name: [ID alarmID user.severity] process(PID) SEVERITY: Alarm text with possible variables

#### Where:

Variable	Description		
Mon DD	Month and date the alarm was logged.		
24:MM:SS	Time the alarm was logged in 24 hour format.		
hostname	Name of the machine on which the alarm was generated.		
process name	Name of the process which logged the alarm.		
alarmID	ID number of the alarm.		
severity	Alarm severity.		
process	Name of the process which logged the alarm.		
PID	Process ID of the process which logged the alarm.		
SEVERITY	Alarm severity.		
Alarm text	Alarm text. This may include variables such as node number.		
	<b>Note:</b> In some cases, the entire alarm text is generated from variables.		

Note: Some alarms from some subsystems may have a different format.

**Example:** This text shows an smsMaster alarm about pending update queues.

```
Mar 30 13:34:54 prodsmp1 smsMaster: [ID 953149 user.warning] smsMaster(17833) WARNING: Pending queue now above 15 (Worst Node 317)
```

#### **Alarm Text and Variables**

The %d and %s symbols represent variables within the alarm text. These values are generated by the subsystem and added to the message when the alarm is raised.

Usually the %d is a number and the %s is text in the context of the message to complete the alarm message. Occasionally other % symbols are also used (for example, %u) for different variables.

#### **Further Information**

For more information about:

- The SMS Alarms subsystem, see Service Management System Technical Guide
- Creating and maintaining the SMS Alarm Relay rule set, see Service Management System User's Guide

# **Plmanager**

## **Errors**

This table defines the error messages for Plmanager.

Alarm Text	Reason	Remedy
Cannot connect to Oracle - exiting	Oracle is not running.	Start Oracle.
Could not make fifo <f> - exiting</f>	The file <f> could not be created.</f>	Check that the "smf_oper" user has sufficient permission to create the file. Check that the disk is not full.
Could not make fifo directory <d> - exiting</d>	The directory <d> could not be created.</d>	Check that the "smf_oper" user has sufficient permission to create the directory. Check that the disk is not full.
Error starting PIbeClient	PlbeClient could not be started.	If PIbeClient should be being started, check PIbeClient exists and is executable.  If PIbeClient should not be being started, ensure there is no pi.PIbeClient section in eserv.config.
Error starting PIprocess	Plprocess could not be started.	Check Plprocess exists and is executable.
Exception reading configuration pi.general.oraUser: check format e.g. "oraUser = "/" - cannot continue	The configuration file entry for pi.general.oraUser has syntax errors.	Check the format of eserv.config.
Exception reading configuration pi.general.synstamp: check format e.g. "synstamp = 'N'" - cannot continue	The configuration file entry for pi.general.synstamp has syntax errors.	Check the format of eserv.config.
Exception reading configuration pi.general.timeout: check format e.g. "timeout = 30" - cannot continue	The configuration file entry for pi.general.timeout has syntax errors.	Check the format of eserv.config.
Exception reading configuration pi.general.mode: check format e.g. "mode = 0" - cannot continue	The configuration file entry for pi.general.mode has syntax errors.	Check the format of eserv.config.
no PIprocesses left	All Piprocesses have stopped so the Pimanager has stopped.	Restart the Plmanager.

Alarm Text	Reason	Remedy
PIbeClient is dead	PlbeClient has stopped. See the PlbeClient output for more details.	Plmanager will attempt to restart the PlbeClient. If this persists, check for additional PlbeClient error messages.
PIprocess for port n is dead	A Plprocess has stopped. See the Plprocess output for more details.	Restart the Plmanager.
PIprocess pid  on port <n> timed out. Sending friendly timeout signal</n>	A PIprocess has timed out.	A timeout may indicate some problem with the database. Check the database is running correctly.
PIprocess pid  on port <n> timed out and not responding. Killing it now.</n>	A Plprocess has timed out and not responded to the time out signal.	A timeout may indicate some problem with the database. Check the database is running correctly.
SQL Error: <message></message>	An Oracle error occurred.	Consult Oracle documentation for the error code.
SQL error <n> reading PI_PORTS - exiting</n>	An oracle error occurred reading the PI_PORTS table.	Consult Oracle documentation for the error code.
Unknown message type n from PI .	The Plprocess on port  has sent an unknown message type to the Plmanager.	Check that the Plprocess on port  is functioning correctly.

# Warnings

This table defines the warning messages for Plmanager.

Alarm Text		Reason	Remedy
SQL Warning:	<message></message>	An oracle warning occurred.	Consult oracle documentation
		_	for the error code.

#### **Notifications**

This table defines the notification messages for Plmanager.

Alarm Text	Reason	Remedy
About to turn debug <on off> for PImanager</on off>	Debug has been turned on or off for the specified Plmanager.	Information only, no action required.
PImanager started	Plmanager has started.	Information only, no action required.
Received SIGHUP - Sending SIGHUP to PIprocesses	Plmanager has received a SIGHUP.	Information only, no action required.
Received SIGINT - Sending SIGINT to PIprocesses and exiting	Plmanager has received a SIGINT.	Information only, no action required.
Received SIGQUIT - Sending SIGTERM to PIprocesses and exiting	Plmanager has received a SIGQUIT.	Information only, no action required.

Alarm Text	Reason	Remedy
	Plmanager has received a SIGTERM.	Information only, no action required.
PIprocesses and exiting		·

# **Plprocess**

# Error codes - general

This table defines the Error code messages for PI command responses.

Fault Code	Alarm Text	Reason	Remedy
70	TOO MANY SESSIONS	The maximum allowed number of connections are already in use.	Check whether the number of active sessions is larger than the allowed sessions set in the PI Administration screen. If it is, either:  • this message is information only and no action is required, or  • increase the number of maximum sessions to accommodate the load.  If it is lower than the specified maximum, contact support with details.
71	LOGON SYNTAX ERROR	Could not parse logon request. The login attempt had a syntax error.	Check that the login command is formatted correctly. Contact Oracle support with details.
72	INVALID LOGON - username, password	Username and/or password are not invalid.	If the username and password should not be recognised by the system, this message is information only, and no action is required.  If the username and password should be recognised, either:

Fault Code	Alarm Text	Reason	Remedy
73	INVALID LOGON - user not allowed on this port	User cannot connect to a server running on the particular port used.	If the port where the attempted logon occurred was not intended as a valid port, this message is information only, and no action is required.  If the port should accept connections, either:  • correct the port number in the PI Administration screen  • check that the user is attempting to connect on the correct port, or  • contact support with details.
74	INVALID LOGON - host	Not allowed to connect from this host.  The host ip address of the machine that is trying to connect to PI may not be defined in the SMF database.	If the host where the attempted logon was from was not intended as a valid host, this message is information only, and no action is required.  If the host should be allowed to make connections, either:
75	UNKNOWN COMMAND	The command is not recognised. The command is not defined in the PI_COMMANDS database.	Check the defined commands using the PI Administration screen.  Contact Oracle support with details.

Fault Code	Alarm Text	Reason	Remedy
76	USER DOES NOT HAVE SUFFICIENT SECURITY	The user does not have the privilege to run the requested command.	If the user who attempted to run the command was not intended to be able to run it, this message is information only, and no action is required.  If the user should be allowed to run this command, either:
77	SYNSTAMP NOT FOUND	The command did not have a synstamp when synstamps are required.	Make sure the command is appended with a synstamp.
78	SYNSTAMP NOT VALID	The synstamp appended to the command was not valid.	Check that the synstamp is larger than the last used synstamp.
79	INVALID OR MISSING MAC	The command was not appended by a security MAC when MACs are required.	Make sure the appended MAC is valid and that the correct MAC key is being used.
80	UNKNOWN PARAMETER FOR COMMAND	A parameter found in the command is recognised.	Check that the command's parameters are as defined in the PI_COMMANDS table by using the PI Administration screen.  Contact Oracle support with details.
81	MISSING PARAMETERS FROM COMMAND	One or more required parameters are missing from the command.	Check that the parameters were provided with the command. Check that the command's required parameters are as defined in the PI_COMMANDS table by using the PI Administration screen. Contact Oracle support with details.
83	DUPLICATE PARAMETER	A parameter appeared twice in the command.	Check whether only one parameter was supplied. Contact Oracle support with details.
84	ERROR RUNNING PROCEDURE	The message sent to the Provisioning Interface was valid, but a failure occurred when attempting to run the service.	Check syslog for errors.  If the problem persists, contact Oracle support with details.

Fault Code	Alarm Text	Reason	Remedy	
85	USER SESSION TERMINATED	The server has shut down the session. The user's session has been terminated by an administrator issuing the kill management command.	If the session was not intended to be shut down, and the problem persists, contact Oracle support with details.	
86	COMMAND TOO BIG	The supplied command was too big.	Check the syntax of the command.	
87	COMMAND SYNTAX ERROR	There is a syntax error in the command.	Check the syntax of the command.  Contact Oracle support with details.	
88	PARAMETER NAME TOO BIG	A parameter name is too big for the command syntax.	Check the parameter name. Contact Oracle support with details.	
89	PARAMETER VALUE TOO BIG	A parameter value is too big for the command syntax.	Check the parameter value. Contact Oracle support with details.	
90	SYNSTAMP OUT OF PLACE	The synstamp was in the wrong place in the command.	Check that the synstamp is in the correct place:  • When MAC security is ON, the synstamp should be between the last command parameter and the MAC.  • When MAC security is OFF, the synstamp should be at the end of the command, after the last command parameter.  Contact Oracle support with details.	
91	TIMEOUT	A timeout has occurred.	A timeout can indicate problems in the database.  If the problem persists and there appears to be no other problems the timeout value can be increased.	
92	INTERNAL ERROR SEE SYSLOG	An internal error has occurred. More information is available from the system log.	If the problem persists, contact Oracle support with details.	
93	ERROR READING REPLY FROM FILE	The PI could not read the results from a DB query that were saved to a temporary file.	Contact Oracle support with details.	

Fault Code	Alarm Text	Reason	Remedy
94	INVALID AUTHENTICATION TOKEN	The authentication token passed has expired or no authentication token was supplied.	The session should be restarted.

### **Errors**

This table defines the error messages for Plprocess.

Alarm Text	Reason	Remedy
Cannot connect to internal DB - cannot continue	The Plprocess could not connect to oracle.	Start Oracle. Check that the oracle environment for the smf_oper UNIX user is correct.
Cannot read from internal DB - cannot continue	The Plprocess could not read from the internal DB.	Check that the PI tables are installed correctly on the SMF machine and have at least one port configured.
Could not create SQL trace file <filename>. All sql tracing will go to PImanager.log. perror for this follows</filename>	Could not create a new file.	Check the next reported error which will describe the file error in detail.
Could not make fifo <f></f>	The fifo file <f> could not be created.</f>	Check that the directory that the file <f> is to be made in is writable by the smf_oper user. Check that the disk is not full.</f>
Could not open fifo <f></f>	The fifo file <f> could not be opened.</f>	Check that the directory that the file <f> is to be made in is writable by the smf_oper user.</f>
Could not rename SQL trace file <filename a=""> to <filename b="">. SQL tracing will continue to <filename a="">. perror for this follows</filename></filename></filename>	Could not create a new file.	Check the next reported error which will describe the file error in detail.
Currently got n connections so deferring database reread until all connections closed	The Plprocess has received an instruction to re-read the internal database. This cannot be done safely with active connections, so will be delayed until all connections are closed	Close all connections to the PI to re-read the database.
Error occurred running C function <f> in shared library &lt;1&gt;. Output is</f>	An error occurred while running the command. Check for other errors preceding this error.	Check preceding errors in the PI commands library errors section below.
Error reading request for user <x> on host <h> - logged off</h></x>	An error occurred reading a command from a remote user. Usually occurs if the user disconnects in the middle of a command. The user is logged off.	The user should re-login.

Alarm Text	Reason	Remedy
Exception reading configuration pi.authentication.time out: check format e.g. "timeout = 0" - cannot continue	The configuration file entry for pi.authentication.timeout has syntax errors.	Check the format of eserv.config.
Exception reading configuration pi.general.logLevel: check format e.g. "loglevel = 0" - cannot continue	The configuration file entry for pi.general.logLevel has syntax errors.	Check the format of eserv.config.
Exception reading configuration pi.general.sqlTraceDir ectory: check format e.g. "sqlTraceDirectory = "/IN/service_packages/PI/tmp/trace/" - cannot continue	The configuration file entry for pi.general.sqlTraceDirectory has syntax errors.	Check the format of eserv.config.
Exception reading configuration pi.localTZ: check the format - cannot continue	The configuration file entry for pi.localTZ has syntax errors.	Check the format of eserv.config.
Exception reading configuration pi.throttling.sendRate : check the format e.g. "sendRate = 0" - cannot continue	The configuration file entry for pi.throttling.sendRate has syntax errors.	Check the format of eserv.config.
Exit due to exception: <pre><message></message></pre>	An internal error has occurred.	Restart the PI. Consult support if persistent.
Oracle connection lost - exiting	The Plprocess connection to the database has been lost. The Plprocess will restart to reconnect to the database cleanly.	Check the logs for related errors. If this occurs persistently, or the Plprocess cannot reconnect, check the oracle database or contact support.
PPID is 1 - PImanager has died and not killed me - exiting	The controlling Plmanager has stopped or been stopped without firstly stopping the Plprocesses.	Restart the Plmanager.
Problems setting up socket - cannot continue	The Plprocess could not bind to the port specified in the database, probably due to another process using the port.	Check that the port is not used by another process. Change the port number using the PI Administration screen.
Security warning. Bad MAC in message from user <x></x>	A user has an incorrect mac on a command.	Check the user and system MAC keys are the same.

Alarm Text	Reason	Remedy
Security warning. Bad synstamp in message from user <x></x>	A user has used an incorrect synstamp.	The next synstamp must be a number larger than the last synstamp returned from the Plprocess or used by the user.
Security warning. Connection from unknown host <h></h>	A connection has been attempted from a host not listed in the hosts database.	If the host is valid it should be entered into the hosts database using the PI administration screens. Then the PImanager should be sent a SIGHUP signal using the PIreread script to force a database re-read.
Security warning. Invalid login attempt (garbage read) from host <h></h>	The username/password were not separated by a comma.	Check that the correct format (username,password;) is being used for the login attempt.
Security warning. Invalid login attempt (user on wrong port) from host <h></h>	A user has tried to connect to a port he is not allowed to connect to.	If the user should be allowed to connect to this port, add the port using the PI administration screens, and then send the PImanager a SIGHUP signal using PIreread.sh to force a database reread.
Security warning. Invalid login attempt (username or password too long) from host <h></h>	The username/password combination was too long.	Check that the correct username and password combination is being used.
Security warning. Invalid login attempt (username, password) from host <h></h>	Either the username or the password is not correct.	Check that the correct username and password combination are being used.
Security warning. User <x> level <n> requested command level <m>.</m></n></x>	A user tried to use a command which has a higher security level than the user's security level.	If the user should be able to use that command, raise the user's security level to at least that command's security level.
Shared Library <1> not loaded: <error message="">.</error>	The shared library could not be loaded. The error message will give more detailed information.	Reinstall the package or patch. Contact Oracle support with details.
SQL Error: <message></message>	An oracle error occurred.	Consult oracle documentation for the error code.
Symbol <s> not found is shared library &lt;1&gt;</s>	The code for the specified command is not in the shared library.	Check that the database entry for the command in PI_COMMANDS is correct.
Timeout occurred.	The processing of the command timed out.	A timeout can indicate problems with the database or billing engine client resulting in long query times.

# Warnings

This table defines the warning messages for Plprocess.

Alarm Text	Reason	Remedy	
Warning: fifos to PImanager not opened.		Check that the files (in /tmp/Plfifo) exist and are read and writable by the smf_oper user.	

### **Notifications**

This table defines the notification messages for Plprocess.

Alarm Text	Reason	Remedy
About to start PIprocess	Plmanager has attempted to start a Plprocess.	Information only, no action required.
About to turn debug <pre><on off> for <command/></on off></pre>	Debug has been turned on or off for the specified PI command.	Information only, no action required.
About to turn debug <on off> for PIbeClient</on off>	Debug has been turned on or off for the specified PlbeClient.	Information only, no action required.
About to turn debug <on off> for PIprocess port</on off>	Debug has been turned on or off for the specified Plprocess.	Information only, no action required.
Debug turned [on off] by PIprocess <n></n>	Plmanager debug has been toggled by a Plprocess	Information only, no action required.
PIprocess started	Plprocess has started.	Information only, no action required.
Received SIGALRM from PImanager PID UID <u>. Timing out.</u>	Plprocess receives a SIGALRM from Plmanager and the time out process starts.	Information only, no action required.
Received SIGALRM from unknown process PID , UID <u>. Not timing out</u>	Plprocess receives a SIGALRM from a process that is not Plmanager. The sending process and user is stated.	Information only, no action required.
Received SIGHUP from PID , UID <u></u>	Plprocess has received a SIGHUP. The sending process and user is stated.	Information only, no action required.
Received SIGINT - Exiting	Plprocess has received a SIGINT.	Information only, no action required.
Received SIGTERM - Exiting	Plprocess has received a SIGTERM.	Information only, no action required.
Received SIGTERM from PID , UID <u></u>	Plprocess receives a SIGTERM. The sending process and user is stated.	Information only, no action required.
Received SIGUSR1 from PID , UID <u></u>	Plprocess receives a SIGUSR1. The sending process and user is stated.	Information only, no action required.
Re-reading internal provisioning database	Plprocess has received a SIGHUP and is re-reading the database.	Information only, no action required.
Shared library <1> successfully loaded.	The shared library has been successfully loaded.	Information only, no action required.

Alarm Text	Reason	Remedy	
Unloading shared library <1>	The database has been re-read after a SIGHUP.	Information only, no action required.	
User <x> logged off on host <h></h></x>	A user had disconnected.	Information only, no action required.	
User <x> logged on from host <h></h></x>	A user has successfully logged on.	Information only, no action required.	

# **Plbatch**

## **Errors**

This table defines the error messages for Plbatch.

Alarm Text	Reason	Remedy
Cannot open result file <file> - exiting</file>	The Plbatch could not open the results file for writing.	Check file permissions for the user running the Plbatch.
Cannot open script file <file> - exiting</file>	The Plbatch could not open the input script file for reading.	Check file permissions for the user running the Plbatch, and that the file exists.
Error reading script file <file> - exiting</file>	The Plbatch could not read the input script file.	Check file permissions for the user running the Plbatch, and that the file exists.
Line <n>: Connect line found when already connected, disconnecting and will reconnect</n>	Syntax error in the input file.	Correct the input file.
Line <n>: Disconnect line when not connected, skipping</n>	Syntax error in the input file.	Correct the input file.
Line <n>: Not connected, not sending command</n>	PI command in input file before the connection line.	Correct the input file.
Usage: PIbatch <script> <server></td><td>Wrong number of command line arguments.</td><td>Usage is "Plbatch <script> <server>"</td></tr></tbody></table></script>		

# **Plbatch XML**

### **Errors**

This table defines the error messages for Plbatch XML.

Alarm Text	Reason	Remedy
unable to connect to PI: <message></message>	Could not connect to Plprocess.	Check the Plprocess is running. Check the hostname is correct. Check the port number is correct.
<pre>unable to read <filename>: open() failed with <message></message></filename></pre>	Unable to read the input file.	Check file permissions for the user running the Plbatch, and that the file exists.
-l not available when reading from stdin	Looping was requested with no input file	Do not specify looping when the input is standard input.

## **Notifications**

This table defines the notification messages for Plbatch XML.

Alarm Text	Reason	Remedy
		Information only, no action required.