

# Oracle Banking Accounts Cloud Service

## Teller Cloud User Guide



14.7.2.0.0

F90268-02

January 2024

The Oracle logo, consisting of a solid red square with the word "ORACLE" in white, uppercase, sans-serif font centered within it.

ORACLE®

Copyright © 2023, 2024, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

# Contents

## 1 Overview of Oracle Banking Branch

---

1.1	Prerequisites	1-1
1.2	About Main Menu	1-2
1.3	Application Layout	1-4
1.3.1	Customer Search	1-4
1.3.2	About Transaction Area	1-5
1.4	Salient Features	1-7
1.5	Keyboard Navigation for Transaction Screens	1-10

## 2 Branch Operations

---

2.1	Open Branch Batch	2-2
2.2	Open Vault Batch	2-3
2.3	Open Teller Batch	2-5
2.4	Current Open Tills	2-7
2.5	Branch Breach Limits	2-8
2.6	Till Vault Position	2-10
2.7	Branch Total Position	2-11
2.8	Close Teller Batch	2-12
2.9	Close Vault Batch	2-15
2.10	Close Branch Batch	2-17
2.11	Book Shortage	2-18
2.11.1	Add Denomination Details	2-19
2.12	Book Overage	2-21

## 3 Transfers

---

3.1	Account Transfer	3-1
3.2	In-House Check Deposit	3-3

## 4 Journal Log

---

4.1	About Electronic and Servicing Journals	4-1
-----	---	-----

4.2	Electronic Journal	4-4
4.3	Servicing Journal	4-7
4.4	Reassign Transactions	4-11

## 5 Customer Transactions

---

5.1	Cash Deposit	5-1
5.1.1	Charge Details	5-4
5.2	Cash Withdrawal	5-6
5.3	Check Withdrawal	5-9
5.4	FX Sale Against Account	5-12
5.5	FX Sale Against Walk-in	5-16
5.6	FX Purchase Against Account	5-19
5.7	FX Purchase Against Walk-in	5-22

## 6 Miscellaneous Transactions

---

6.1	Miscellaneous Customer Debit	6-1
6.2	Miscellaneous Customer Credit	6-4
6.3	Miscellaneous GL Debit	6-7
6.4	Miscellaneous GL Credit	6-9
6.5	Miscellaneous GL Transfer	6-12
6.6	Miscellaneous Transfer	6-14

## 7 Branch Maintenance

---

7.1	Maintain Denominations	7-2
7.2	Maintain Inter Branch Transit Account	7-4
7.3	Maintain Teller Branch Parameters	7-6
7.4	Maintain Branch User Preferences	7-7
7.5	Maintain Channel Limits	7-9
7.6	Maintain Function Code Definitions	7-11
7.7	Maintain Branch Role Limits	7-15
7.8	Create Charge Pricing Maintenance	7-17
7.9	View Charge Pricing Maintenance	7-18
7.10	Maintain Charge Definitions	7-19
7.11	Maintain Denomination Variance	7-21
7.12	Maintain Function Code Preferences	7-23
7.13	Maintain Accounting and Settlements	7-28
7.14	Maintain Reject Codes	7-31
7.15	Maintain Account Group	7-33
7.16	Maintain External System	7-34

7.17	Maintain External Bank Codes	7-36
7.18	Maintain Charge Decisions	7-38
7.19	Maintain Charge Condition Group	7-39
7.19.1	Additional Information on Parameters	7-41
7.20	Maintain Customer Group	7-42
7.21	Maintain Default Authorizer	7-44
7.22	Maintain Branch Group	7-45
7.23	Static Data	7-47

## 8 Till-Vault Operations

---

8.1	Buy Cash from Vault	8-1
8.2	Buy Cash from Till	8-3
8.3	Buy Cash from Currency Chest	8-4
8.4	Sell Cash to Currency Chest	8-6
8.5	Sell Cash to Till	8-7
8.6	Denomination Exchange	8-8
8.7	Sell Cash to Vault	8-9
8.8	Inter Branch Transactions	8-11
8.8.1	Inter Branch Transaction Request	8-12
8.8.2	Inter Branch Transaction Input	8-14
8.8.3	Inter Branch Transaction Liquidation	8-16

## A Functional Activity Codes

---

## B Error Codes and Messages

---

## C List of Function Codes

---

## D Order of Replacing Parameters with Wild Card Entries

---

## E Static Maintenance Parameters

---

## Index

---

# Preface

- [Purpose](#)  
This guide helps you to familiarize yourself with the Oracle Banking Branch application. It gives an overview of the module and explains all the maintenances required for its smooth functioning. It also takes you through the different types of transactions that can be handled through this module.
- [Audience](#)
- [Documentation Accessibility](#)
- [Diversity and Inclusion](#)
- [Conventions](#)
- [Related Resources](#)
- [Screenshot Disclaimer](#)
- [Acronyms and Abbreviations](#)  
The following acronyms and abbreviations are used in this guide:
- [Basic Actions](#)  
Most of the screens contain icons to perform all or a few of the basic actions. The actions which are called here are generic, and it varies based on the usage and the applicability. The table below gives a snapshot of them:
- [Symbols and Icons](#)

## Purpose

This guide helps you to familiarize yourself with the Oracle Banking Branch application. It gives an overview of the module and explains all the maintenances required for its smooth functioning. It also takes you through the different types of transactions that can be handled through this module.

## Audience

This guide is intended for the Branch Tellers, Vault Operators, and Branch Supervisors to provide quick and efficient service to customers and prospects of your bank.

## Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

### Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

## Diversity and Inclusion

Oracle is fully committed to diversity and inclusion. Oracle respects and values having a diverse workforce that increases thought leadership and innovation. As part of our initiative to build a more inclusive culture that positively impacts our employees, customers, and partners, we are working to remove insensitive terms from our products and documentation. We are also mindful of the necessity to maintain compatibility with our customers' existing technologies and the need to ensure continuity of service as Oracle's offerings and industry standards evolve. Because of these technical constraints, our effort to remove insensitive terms is ongoing and will take time and external cooperation.

## Conventions

The following text conventions are used in this document:

Convention	Meaning
<b>boldface</b>	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
<code>monospace</code>	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

## Related Resources

The related documents are as follows:

- *Getting Started User Guide*
- *Current Account and Savings Account User Guide*
- *Servicing Configurations User Guide*

## Screenshot Disclaimer

Personal information used in the interface or documents is dummy and does not exist in the real world. It is only for reference purposes.

## Acronyms and Abbreviations

The following acronyms and abbreviations are used in this guide:

**Table Acronyms and Abbreviations**

Acronym/ Abbreviation	Description
<b>CASA</b>	Current Account and Saving Account
<b>CCY</b>	Currency


Table (Cont.) Acronyms and Abbreviations

Acronym/ Abbreviation	Description
EJ	Electronic Journal
FX	Foreign Exchange
GL	General Ledger
HO	Head Office
LCY	Local Currency
LOV	List of Values
System	Unless specified, it shall always refer to Oracle Banking Branch.

## Basic Actions

Most of the screens contain icons to perform all or a few of the basic actions. The actions which are called here are generic, and it varies based on the usage and the applicability. The table below gives a snapshot of them:

Table Common Icons and its Definitions

Icon	Description
<b>Submit</b>	Click <b>Submit</b> to complete the transaction after you specify all the input parameters for a particular transaction.
<b>Cancel</b>	Click <b>Cancel</b> to cancel the transaction input midway without saving any data.
<b>Clear</b>	Click <b>Clear</b> to clear the transaction input data. The system displays a pop-up screen with confirmation to clear data. You can click <b>OK</b> to confirm or click  icon to retain the data.
<b>Query</b>	On completion of input of necessary parameters, click <b>Query</b> to fetch and display the details.
<b>Save</b>	Click <b>Save</b> to save the details specified on the screen.
<b>Exit</b>	Click <b>Exit</b> to close the screen and go to the Homepage.
<b>OK</b>	Click <b>OK</b> to confirm the details on the pop-up screen.

## Symbols and Icons

The following are the symbols you are likely to find in this guide:

Table Symbols




















Symbol	Function
	Add icon




Table (Cont.) Symbols

Symbol	Function
	Add a row
	Edit icon
	Delete icon
	Calendar icon
	Close icon
	Delete a row
	Grid view
	Increase/Decrease value
	List view
	Maximize
	Minimize
	Navigate to the first page
	Navigate to the last page
	Navigate to the next page
	Navigate to the previous page
	Open a list
	Perform search
	Refresh

The following shortcut keys can be used only for the screens which have the icons specified in the Function column:

Table Shortcut Keys

Shortcut Key	Function
Tab	Used to shift focus from one input field to the other.   <b>Note:</b> The last field of the last accordion will shift focus to <b>Submit/Cancel</b> button.
Alt + S	Used to select <b>Submit</b> button.
Alt + C	Used to select <b>Clear</b> button.
Alt + X	Used to select <b>Cancel</b> button.
Alt + A	Used to select <b>Charge Details</b> data segment.
Alt + Y	Used to select <b>Denominations</b> data segment.

# 1

## Overview of Oracle Banking Branch

Oracle Banking Branch is a retail banking application that gives a 360-degree view of the customer and financial transactions to the Teller of the bank.

Oracle Banking Branch you as the Teller, to provide better customer-focused services as well as cross-sell and up-sell the other products and services of the bank. A typical transaction under a branch is classified into the following stages:

**Table 1-1 Transaction Stages**

Stage	Description
<b>Teller Request</b>	In this stage, the Teller captures the transaction request and transaction enrichment.
<b>Authorization</b>	In this stage, the Supervisor authorizes the request.
<b>Teller Resubmission</b>	The Resubmission stage is applicable only for certain transactions.

This topic contains the following subtopics:

- [Prerequisites](#)  
Before you begin performing transactions, you need to log in to the Oracle Banking Accounts Cloud Service **Home** screen.
- [About Main Menu](#)  
The Teller Main Menu is a Mega Menu that makes all the menu items visible at once. It is a large panel divided into groups of menu items, which simplifies the navigation.
- [Application Layout](#)  
The general layout of the Oracle Banking Branch application consists of the main menu, customer search, transaction area including customer summary, and additional widgets available to display the `Current Till Position` and frequently used transaction icons.
- [Salient Features](#)  
Learn about the salient features of the Oracle Banking Branch application.
- [Keyboard Navigation for Transaction Screens](#)  
The keyboard navigation can be used as an alternative method to navigate through interactive elements on a screen – fields, buttons, data segments, tables, etc. It can be used to navigate through the application, input the necessary values, and perform the transactions.

### 1.1 Prerequisites


Before you begin performing transactions, you need to log in to the Oracle Banking Accounts Cloud Service **Home** screen.

For information on how to log in, refer to the *Oracle Banking Getting Started User Guide*.

To launch Oracle Banking Branch through Oracle Banking Accounts Cloud Service:

1. Log in to the Oracle Banking Accounts Cloud Service **Home** screen. For information on how to log in, refer to the *Oracle Banking Getting Started User Guide*.  
The Oracle Banking Accounts Cloud Service **Home** screen is displayed.
2. On the **Home** screen, click **Teller**.  
The Oracle Banking Branch **Home** screen is displayed.

**Figure 1-1 Home Screen**



## 1.2 About Main Menu

The Teller Main Menu is a Mega Menu that makes all the menu items visible at once. It is a large panel divided into groups of menu items, which simplifies the navigation.

The menu items are grouped based on the type of operation performed. In addition, the **Menu Item Search** can be used to search and select a specific screen from any of the main menu items. For more information on menus, refer to [Figure 1-2](#) and [Table 1-2](#).

Figure 1-2 Mega Menu Teller




Table 1-2 Menu Items – Description

Menu	Description
<b>Branch Operations</b>	Branch Manager, Vault Teller, or Teller can use <b>Branch Operations</b> to cover the internal activities done at the branch where the Customer is not involved. This facilitates branch, vault, Till opening, or closing for the day and monitoring the transactions done during the day, and Cash Balancing.
<b>Till-Vault Operations</b>	Vault Teller or Teller can use <b>Till-Vault Operations</b> to monitor the cash and currency boxes for the day and to perform cash transfers from or to the Vault or Till as and when required.
<b>Customer Transactions</b>	Teller can use <b>Customer Transactions</b> to perform financial transactions for customer accounts, which includes, cash deposits, cash withdrawals, and check withdrawals.
<b>Miscellaneous Transactions</b>	Teller can use <b>Miscellaneous Transactions</b> to perform General Ledger transactions such as miscellaneous debit and credit transactions against a Customer's CASA account and GL account.
<b>Transfers</b>	Teller can use <b>Transfers</b> to perform account transfer and in-house check deposit transactions.
<b>Journal Log</b>	Teller or Supervisor can use <b>Journal Log</b> to view the status of transactions performed by them. Also, it allows to resubmit or reject an incomplete transaction, or to reverse a completed transaction.
<b>Branch Maintenance</b>	<b>Branch Maintenance</b> covers a set of definitions maintained to perform the branch-based operations, transactions, and services.

You can select an operation using any of the following methods:

- From the **Home** screen, navigate to the left menu and then click the necessary operation.
- Click the **Frequent Operations** widget placed at the right side of the transaction area.

## 1.3 Application Layout

The general layout of the Oracle Banking Branch application consists of the main menu, customer search, transaction area including customer summary, and additional widgets available to display the `Current Till Position` and frequently used transaction icons.

This topic contains the following subtopics:

- [Customer Search](#)  
The **Customer Search** is located in the **Branch Dashboard** and **Teller Transaction** screens. It is used to query and find a specific customer account.
- [About Transaction Area](#)  
The transaction area consists of a transaction panel, a **Customer Information** widget, and additional widgets within the **Teller Transaction** screens.

### 1.3.1 Customer Search

The **Customer Search** is located in the **Branch Dashboard** and **Teller Transaction** screens. It is used to query and find a specific customer account.

You can use **Customer Search** to query and find a specific customer account with one of the following information:

- Customer ID
- Customer Name
- Account Number

To find a specific customer account:

1. On the **Home** screen or the transaction screen, in the Customer Search widget, click **Search** icon.

The **Customer Search** screen is displayed.

Figure 1-3 Customer Search

2. On the **Customer Search** screen, query the details. For more information on fields, refer to the field description table.

Table 1-3 Customer Search - Field Description

Field	Description
<b>Customer ID</b>	Specify the customer ID which the details need to be queried.
<b>Customer Name</b>	Specify the name of the customer for which the details need to be queried.
<b>Account Number</b>	Specify the account number for which the details need to be queried.
<b>Search</b>	Click <b>Search</b> to get the results for the specified <b>Customer ID</b> , <b>Customer Name</b> , or <b>Account Number</b> .
<b>Reset</b>	Click <b>Reset</b> to clear the search results.
<b>Customer Results</b>	Displays the customer search results.
<b>Customer ID</b>	Displays the customer ID.
<b>Customer Name</b>	Displays the customer's name.
<b>Account Details</b>	Displays the account search results.
<b>Account Number</b>	Displays the account number.
<b>Account Name</b>	Displays the description of the account.
<b>Account Currency</b>	Displays the currency of the account.

## 1.3.2 About Transaction Area

The transaction area consists of a transaction panel, a **Customer Information** widget, and additional widgets within the **Teller Transaction** screens.

A sample of the transaction area is shown below:

**Figure 1-4 Transaction Area**

### Transaction Header

The transaction header is specific to each transaction screen. The following details are provided in the transaction header:

**Table 1-4 Transaction Header**

Item	Description
<b>Transaction Screen Name</b>	Displays the name of the selected transaction screen.
<b>Customer Search</b>	For information on the <b>Customer Search</b> , refer to <a href="#">Customer Search</a> .
<b>Branch Date</b>	Displays the current branch date.

### Transaction Panel


The transaction panel consists of the data segments with the necessary input fields and action buttons. Users need to specify the details in the fields to perform the transactions.

### Customer Information

The **Customer Information** widget provides the details about the customer that are validated during transaction submission.



Table 1-5 Customer Information

Field	Description
<b>Display Option</b>	<p>The <b>Customer Information</b> widget is displayed only if this option is selected.</p> <div style="border: 1px solid #0070C0; padding: 10px; margin: 10px 0;"> <p> <b>Note:</b></p> <p>The display option is based on the <b>Y/N</b> static maintenance maintained in the function code indicator table. You need to enable it in the <b>SRV_TM_BC_FUNCTION_INDICATOR</b> table.</p> </div>
<b>Customer's Image</b>	Displays the image of the customer.
<b>Customer's Name</b>	Displays the name of the customer.
<b>KYC Status</b>	Displays the KYC status of the customer's details.
<b>Signature</b>	Displays the signature of the customer.
<b>Account Details</b>	Displays the details of the customer account.
<b>Address Details</b>	Displays the address details of the customer.
<b>Contact Details</b>	Displays the contact details of the customer.

## 1.4 Salient Features

Learn about the salient features of the Oracle Banking Branch application.

The salient features are as follows:

Table 1-6 Salient Features

Feature	Description
<b>Generation of Teller Sequence Number</b>	<p>The system generates a unique Teller Sequence Number and displays an information message <code>Teller Sequence Number nnn</code> indicating the generated number after submission of each teller transaction. The generated sequence number is also displayed at the following levels:</p> <ul style="list-style-type: none"> <li>• Completion</li> <li>• Authorization Submission</li> <li>• Re-submission</li> <li>• Reversal</li> <li>• Rejection</li> </ul>

Table 1-6 (Cont.) Salient Features

Feature	Description
<p><b>Transaction Approval</b></p>	<p>When you perform a transaction for an amount greater than the allowed limit, it needs approval from the Supervisor. Based on the <b>Assignment Mode</b> in <b>Function Code Preferences</b> screen, the following conditions apply:</p> <ul style="list-style-type: none"> <li>• <b>Manual</b> – The system will show a list of approval if the request status is <b>Approval</b>.</li> <li>• <b>Auto</b> – The transaction is automatically assigned to the default authorizer if the request status is <b>Approval</b>.</li> </ul> <p>The transaction approval flow consists of the following steps:</p> <ul style="list-style-type: none"> <li>• Initiation</li> <li>• Pending Approval</li> <li>• Approved (Sent Back)</li> <li>• Completed</li> </ul> <p>For more information on transaction approval flow, refer to <a href="#">Table 1-7</a>.</p>
<p><b>Transaction Reversal with Approval</b></p>	<p>A transaction can be reversed with auto-approval or approval from the Supervisor. Based on the <b>Assignment Mode</b> in <b>Function Code Preferences</b> screen, the following conditions apply:</p> <ul style="list-style-type: none"> <li>• <b>Manual</b> – The system will show a list of approval if the request status is <b>Approval</b>.</li> <li>• <b>Auto</b> – The transaction is automatically assigned to the default authorizer if the request status is <b>Approval</b>.</li> </ul> <p>The transaction approval flow consists of the following steps:</p> <ul style="list-style-type: none"> <li>• Completed</li> <li>• Pending Approval</li> <li>• Approved (Sent Back)</li> <li>• Completed</li> <li>• Reversed</li> </ul> <p>For more information on transaction flow for reversal with approval, refer to <a href="#">Table 1-8</a>.</p>
<p><b>Transaction Reversal</b></p>	<p>A transaction can be manually reversed only when it is authorized and completed from the <b>Journal Log</b>.</p> <p>When you reverse a transaction, the data remains in the system with the status <b>Reversed</b> and the accounting entries are reversed. Also, this will update the Till Balance for the currencies (for cash transactions), wherever applicable.</p> <p>You can select the transaction to be reversed from the transaction screen. If the reversal is applicable for the function code, the <b>Reversal</b> icon will be enabled. When you click this icon, the reversal request will be initiated.</p> <p>If cash transactions are reversed, the system validates the following:</p> <ul style="list-style-type: none"> <li>• the Till used for the reversal is the same as that used in the original transaction</li> <li>• the denominations are input</li> <li>• a batch is open</li> </ul>

Table 1-6 (Cont.) Salient Features


Feature	Description
Transaction Rejection	<p>You can manually reject the authorized customer transactions from the Teller <b>Journal Log</b>.</p> <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>When you reject a transaction, the data remains in the system with the contract status <b>Discarded</b> and no further action is allowed on the transaction.</p> </div>

Table 1-7 Transaction Approval Flow

Stage	Description
<b>Initiation to Pending Approval</b>	<p>If the transaction amount exceeds the limit defined in Branch User Limits and on click of <b>Submit</b>, the system shows a popup message <code>Amount exceeds limit for this transaction</code>, and request status is shown as <b>Approval</b>.</p> <p>If assignment mode is manual and on click of <b>Confirm</b>, the system shows a list of approval based on branch code, transaction amount, currency, and function code. The user can give a narrative and click <b>Submit for Approval</b> button.</p>
<b>Pending Approval to Pending</b>	<p>The Approver/Supervisor needs to log in and fetch the transaction from <b>Journal Log</b> with transaction status as <b>Pending Approval</b>. The Supervisor can approve the pending transaction by clicking <b>Approve/Reject</b> with the supervisor comment.</p>
<b>Pending to Completed</b>	<p>The user needs to fetch the transaction from <b>Journal Log</b> with transaction status as <b>Sent Back</b> and click <b>Submit</b>.</p>
<b>Override Flow (Initiation to Completed)</b>	<p>Based on the branch maintenance setup at certain levels like Function Code, Function Code Preferences, Branch User Limits, and Branch role limits, if the transaction is validated with any warning override, the system shows a popup message with request status as <b>Warning</b>. Once the user confirms, the transaction status will be shown as <b>Completed</b>.</p>

Table 1-8 Transaction Reversal with Approval Flow

Stage	Description
<b>Completed to Pending Approval</b>	<p>The completed transaction can be selected from the <b>Electronic Journal</b> screen. Once you click <b>Reverse</b>, the system shows a popup message <code>Amount required for Reversal</code> and requests changes to <b>Approval</b>.</p> <p>If assignment mode is manual and on click of <b>Confirm</b>, the system shows a list of approval based on branch code, transaction amount, currency, and function code. The user can give a narrative and click <b>Submit for Approval</b> button.</p>

**Table 1-8 (Cont.) Transaction Reversal with Approval Flow**

Stage	Description
<b>Pending Approval to Pending</b>	The Approver/Supervisor needs to log in and fetch the transaction from <b>Journal Log</b> with transaction status as <b>Pending Approval</b> . The Supervisor can approve the pending transaction by clicking <b>Approve/Reject</b> with the supervisor comment.
<b>Pending to Reversed</b>	The user needs to fetch the transaction from <b>Journal Log</b> with transaction status as <b>Sent Back</b> and click <b>Submit</b> .
<b>Override Flow (Completed to Approval)</b>	The user needs to select the completed transaction in the <b>Electronic Journal</b> screen and click <b>Reverse</b> . If the <b>Reversal Requires Authorization</b> is enabled in the <b>Function Code Definition</b> screen, the system displays an information message to select the Approver based on Manual or Auto assignment mode. After selecting the approver internally, reversal override will be called and request status will be updated as <b>Approval</b> .

## 1.5 Keyboard Navigation for Transaction Screens

The keyboard navigation can be used as an alternative method to navigate through interactive elements on a screen – fields, buttons, data segments, tables, etc. It can be used to navigate through the application, input the necessary values, and perform the transactions.

The keyboard navigation for various operations and their descriptions are as follows:

**Table 1-9 Keyboard Navigation**

Operation	Description of Navigation
<b>Input Values in Fields</b>	After you launch the transaction screen, press the <b>Tab</b> key to navigate to the desired field, and specify the value.
<b>Select Date</b>	To select the appropriate date, perform the following steps: <ol style="list-style-type: none"> <li>1. Press <b>Tab/Shift + Tab</b> keys to navigate to the desired calendar icon.</li> <li>2. Use <b>Arrow</b> keys to navigate to the desired date.</li> <li>3. Press <b>Enter</b> key or <b>Spacebar</b> to select the date.</li> </ol>
<b>Select from Drop-down Lists</b>	To select a value from the drop-down list, perform the following steps: <ol style="list-style-type: none"> <li>1. Press <b>Tab/Shift + Tab</b> keys to navigate to the desired drop-down list.</li> <li>2. Use <b>Arrow</b> keys to navigate to the desired value.</li> <li>3. Press <b>Enter</b> key to select the value.</li> </ol>

Table 1-9 (Cont.) Keyboard Navigation

Operation	Description of Navigation
<b>Select from List of Values</b>	<p>To select a value from the list of values, perform the following steps:</p> <ol style="list-style-type: none"> <li>1. Press <b>Tab/Shift + Tab</b> keys to navigate to the desired list of values.</li> <li>2. Press <b>Enter</b> key or <b>Spacebar</b> to enter into the list of values.</li> <li>3. If the exact value is known, specify the value in the search field, and press the <b>Tab</b> key to navigate to the <b>Fetch</b> button. Press <b>Enter</b> key to select the <b>Fetch</b> button. The results will be fetched based on the input value.</li> <li>4. Press the <b>Tab</b> key to navigate to the results.</li> <li>5. Use <b>Arrow</b> keys to navigate to the desired value.</li> <li>6. Press <b>Spacebar</b> to select the value.</li> </ol>
<b>Navigating through Tables</b>	<p>To specify/select value in the fields/cells of a table, perform the following steps:</p> <ol style="list-style-type: none"> <li>1. Press <b>Tab/Shift + Tab</b> keys to navigate to the desired data segment, and navigate to the desired table row.</li> <li>2. Press <b>Enter</b> key to enter into the data fields/cells.</li> <li>3. Specify the necessary value in the fields.</li> <li>4. If there are more cells in the row, use the <b>Tab</b> key to navigate to the other cells and specify the values.</li> <li>5. After you specify the values in the cells, press the <b>Esc</b> key to change the selection from cell to row.</li> <li>6. Press the <b>Tab</b> key to navigate to the other tables/data segments/fields/buttons.</li> </ol>
<b>Select Option Buttons/ Icons</b>	<p>To select option buttons, perform the following steps:</p> <ol style="list-style-type: none"> <li>1. Press <b>Tab/Shift + Tab</b> keys to navigate to the desired option button.</li> <li>2. Press <b>Enter</b> key or <b>Spacebar</b> to select the desired option button.</li> </ol>
<b>Perform Transaction</b>	<p>To specify/select the necessary values and submit a transaction using keyboard navigation, perform the following steps:</p> <ol style="list-style-type: none"> <li>1. Use the appropriate shortcut keys to navigate to the fields, buttons, data segments, tables, etc., and specify/select the necessary values.</li> <li>2. After you specify the necessary values, use appropriate shortcut keys to select <b>Submit</b> button to complete a transaction.</li> </ol>

# 2

## Branch Operations

The Branch Manager, Vault Teller, or Teller can use branch operations to perform the internal activities done at the branch where the customer is not involved.

This topic contains the following subtopics:

- [Open Branch Batch](#)  
The **Open Branch Batch** screen is used to initiate the branch operations for the posting date. The Supervisor or Branch Manager with necessary access can open this screen.
- [Open Vault Batch](#)  
The Vault Teller can use **Open Vault Batch** screen to open a vault batch on a specified date.
- [Open Teller Batch](#)  
The **Open Teller Batch** screen is used to open a teller batch on a specified date.
- [Current Open Tills](#)  
The **Current Open Tills** screen is used to view the open tills or vault for the branch during the day or before performing the end-of-day activity.
- [Branch Breach Limits](#)  
The **Branch Breach Limits** screen helps to view the details of Till or Vault, which is breaching the currency limits along with the current balance position.
- [Till Vault Position](#)  
The **Till Vault Position** screen is used to view the cash position of all the currencies at any time for the *Teller ID* or *Vault ID*, which is logged in for the current posting date. It also shows the denomination details.
- [Branch Total Position](#)  
The supervisor can use this screen to view the currency-wise cash position of all the Tellers and Vault Teller on the posting date for the logged-in branch.
- [Close Teller Batch](#)  
The **Close Teller Batch** screen is used to close the teller batch for the given posting date.
- [Close Vault Batch](#)  
The **Close Vault Batch** screen is used to close the vault batch for a specific date.
- [Close Branch Batch](#)  
The **Close Branch Batch** screen is used to close the branch batch after confirming that all the branch transactions have been accounted for in the account books.
- [Book Shortage](#)  
The Teller or Vault Teller can use the **Book Shortage** screen to book the shortage if the actual or physical cash present is less than the system cash.
- [Book Overage](#)  
The Teller or Vault Teller can use this screen to book the physical cash held in a particular currency, which exceeds the cash in that currency shown in the system.

## 2.1 Open Branch Batch

The **Open Branch Batch** screen is used to initiate the branch operations for the posting date. The Supervisor or Branch Manager with necessary access can open this screen.

The Teller or Vault Teller can perform the branch operations only after the branch batch is submitted for the posting date. When a branch batch is closed for the day, the system derives the next working day automatically, based on the branch calendar.

To open a branch batch:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Operations**, click **Open Branch Batch** or specify **Open Branch Batch** in the search icon bar and select the screen.


The **Open Branch Batch** screen is displayed.

**Figure 2-1 Open Branch Batch**



2. On the **Open Branch Batch** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 2-1 Open Branch Batch - Field Description**

Field	Description
<b>Posting Date</b>	<p>Indicates the date on which the branch batch needs to be opened.</p> <div style="border: 1px solid #0070C0; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>By default, the system displays the current date.</p> </div>

3. Click **Submit**.

The branch batch is opened for the specified posting date.

**Note:**

Opening branch batch indicates to the head office that the branch is open for business operations on the specified posting date. You can open a Teller batch for the posting date only after the branch batch is opened.

## 2.2 Open Vault Batch

The Vault Teller can use **Open Vault Batch** screen to open a vault batch on a specified date.

On the specified posting date, the Vault Teller can open only one vault batch. To open another vault batch, the vault batch which is opened previously needs to be closed. All the tellers buy additional cash and sell their excess cash to the Vault Teller. When this screen is launched, the system will default the cash balances.

To open a vault batch:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Operations**, click **Open Vault Batch** or specify **Open Vault Batch** in the search icon bar and select the screen.



The **Open Vault Batch** screen is displayed.

**Figure 2-2 Open Vault Batch**

2. On the **Open Vault Batch** screen, specify the fields. For more information on fields, refer to the field description table.



**Table 2-2 Open Vault Batch - Field Description**

Field	Description
<b>Posting Date</b>	<p>Indicates the date on which the vault batch needs to be opened.</p> <div style="border: 1px solid #0070C0; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>By default, the system displays the current date.</p> </div>
<b>Currency</b>	Displays the currency code.
<b>Total Cash</b>	Specify the total cash for a particular currency, physically present in the bank vault, at the beginning of the current posting date.
<b>Cash Available</b>	<p>Displays the system calculated cash for a particular currency, which is available in the vault at the beginning of the current posting date.</p> <div style="border: 1px solid #0070C0; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>The amount shown in this column depends on the cash transactions that were carried out by the vault until the last posting date.</p> </div>
<b>Shortage/Overage Amount</b>	Displays the difference between the total cash and the cash available in the Vault, at the end of the current posting date.
<b>Currency</b>	Displays the currency code.
<b>Denomination</b>	Displays the denomination code.
<b>Total Units</b>	Specify the total units available while closing the batch.
<b>Total Value</b>	Displays the total value based on the total units.
<b>System Units</b>	Displays the units available in the system.
<b>System Total</b>	Displays the total value available in the system.
<b>Shortage/Overage Units</b>	Displays the shortage/overage units.
<b>Shortage/Overage Amount</b>	Displays the shortage/overage amount.
<b>Total Cash Amount</b>	Displays the total cash amount.
<b>Denomination Total</b>	Displays the total denomination value with the currency.
<b>Validate Denominations</b>	Click this button to calculate and display the <b>Total Cash</b> and <b>Shortage/Overage Amount</b> fields based on the currency selected.

3. Click **Submit**.

The vault batch is opened for the specified posting date.

 **Note:**

During the vault batch opening, the system will internally transfer the available balance from the Primary vault of the branch to the current open Vault ID. The Vault Teller can perform the relevant vault operations for the posting date. The system does not allow to open the vault batch if the physical cash entered is not the same as the system cash.

## 2.3 Open Teller Batch

The **Open Teller Batch** screen is used to open a teller batch on a specified date.


A Teller can initiate the teller batch with the current cash position that has been retained from the previous day or start with zero cash and subsequently buy cash from the vault. The system will default the cash balances on opening a teller batch.

To open a teller batch:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Operations**, click **Open Teller Batch** or specify **Open Teller Batch** in the search icon bar and select the screen.

The **Open Teller Batch** screen is displayed.

**Figure 2-3 Open Teller Batch**



2. On the **Open Teller Batch** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 2-3 Open Teller Batch - Field Description**




Field	Description
<b>Posting Date</b>	<p>Indicates the date on which the vault batch needs to be opened.</p> <div style="border: 1px solid #0070C0; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>By default, the system displays the current date.</p> </div>
<b>Currency</b>	Displays the currency code.
<b>Total Cash</b>	Specify the total cash for a particular currency, physically present in the bank teller, at the beginning of the current posting date.
<b>Cash Available</b>	<p>Displays the system calculated cash for a particular currency, which is available in the vault at the beginning of the current posting date.</p> <div style="border: 1px solid #0070C0; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>The amount shown in this column depends on the cash transactions that were carried out by the vault until the last posting date.</p> </div>
<b>Shortage/ Overage Amount</b>	<p>Displays the difference between the total cash and the cash available with the Teller, at the end of the current posting date. Based on this difference, the overage or the shortage amount is displayed.</p> <div style="border: 1px solid #0070C0; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>An overage indicates that the physical cash with the Teller is more than the available cash as calculated by the system. A shortage indicates that the available cash calculated by the system is more than the physical cash present with the Teller.</p> </div>
<b>Currency</b>	Displays the currency code.
<b>Denomination</b>	Displays the denomination code.
<b>Total Units</b>	Specify the total units available while closing the batch.
<b>Total Value</b>	Displays the total value based on the total units.
<b>System Units</b>	Displays the units available in the system.
<b>System Total</b>	Displays the total value available in the system.
<b>Shortage/Overage Units</b>	Displays the shortage/overage units.
<b>Shortage/Overage Amount</b>	Displays the shortage/overage amount.

Table 2-3 (Cont.) Open Teller Batch - Field Description

Field	Description
<b>Total Cash Amount</b>	Displays the total cash amount.
<b>Denomination Total</b>	Displays the total denomination value with the currency.
<b>Validate Denominations</b>	Click this button to calculate and display the <b>Total Cash</b> and <b>Shortage/Overage Amount</b> fields based on the currency selected.

- Click **Submit**.

The teller batch is opened for the specified posting date.

 **Note:**

The Teller can perform the relevant teller operations for the posting date. The system does not allow to open the vault batch if the physical cash entered is not the same as the system cash. The system also allows to re-open the Teller batch for the current system date.

## 2.4 Current Open Tills

The **Current Open Tills** screen is used to view the open tills or vault for the branch during the day or before performing the end-of-day activity.

The branch user can use this screen to view the list of logged-in Tellers and to view the following transactions under each Teller or Vault Teller's ID:


- Pending
- User Working
- Assigned

To view the open tills or vault:

- On the **Home** screen, from **Teller** mega menu, under **Branch Operations**, click **Current Open Tills** or specify **Current Open Tills** in the search icon bar and select the screen.

The **Current Open Tills** screen is displayed.

Figure 2-4 Current Open Tills




Current Open Tills					
Branch Code 006		Posting Date March 30, 2018			
Refresh					
User ID	User Name	Till/Vault Indicator	User Working	Pending Transactions	Assigned Transactions
REMOTLR1		T	Y	234	0
SIDDHARTH		T	Y	1	0
SIDDHARTH		V	Y	1	0
NAVEENTR1		T	Y	0	0
NAVEENTR2		T	N	0	1

Page 1 of 8 (1-5 of 36 items) < 1 2 3 4 5 ... 8 >

2. On the **Current Open Tills** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 2-4 Current Open Tills - Field Description**

Field	Description
<b>Branch Code</b>	Displays the logged-in branch.
<b>Posting Date</b>	Indicates the date on which the current open tills need to be enquired.  <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b> By default, the system displays the current date.</p> </div>
<b>Refresh</b>	Click <b>Refresh</b> to refresh the details.
<b>User ID</b>	Displays the list of Tellers or Vault Tellers of the branch.
<b>User Name</b>	Displays the name of the user.
<b>Till/Vault Indicator</b>	Displays the check box if the <b>User ID</b> is a Vault Teller.
<b>User Working</b>	Displays the user working as Y or N.
<b>Pending Transactions</b>	Displays the number of pending transactions for the Teller or Vault Teller.
<b>Assigned Transactions</b>	Displays the number of assigned transactions for the Teller or Vault Teller.

## 2.5 Branch Breach Limits

The **Branch Breach Limits** screen helps to view the details of Till or Vault, which is breaching the currency limits along with the current balance position.

In addition, the branch supervisor can view the branch's total cash position and its breaching limits for the posting date.

To view the branch breaching limits:


1. On the **Home** screen, from **Teller** mega menu, under **Branch Operations**, click **Branch Breach Limits** or specify **Branch Breach Limits** in the search icon bar and select the screen.

The **Branch Breach Limits** screen is displayed.

Figure 2-5 Branch Breach Limits

2. On the **Branch Breach Limits** screen, specify the fields. For more information on fields, refer to the field description table.

Table 2-5 Branch Breach Limits - Field Description

Field	Description
<b>Branch Code</b>	Displays the logged-in branch.
<b>Posting Date</b>	Indicates the date on which the branch breaching limits needs to be enquired.  <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;"> <p> <b>Note:</b> By default, the system displays the current date.</p> </div>
<b>Refresh</b>	Click this icon to refresh the details.
<b>Tills Breaching Limit</b>	Specify the fields under this section.
<b>User ID</b>	Displays the list of Tellers/Vault Tellers of the branch.
<b>Vault User</b>	Displays the checkbox if the <b>User ID</b> is a Vault Teller.
<b>Currency</b>	Displays the list of currencies in which the <b>User ID</b> has performed the transactions.
<b>Minimum Limit</b>	Displays the minimum till balance that needs to be maintained for the <b>User ID</b> and currency combination.
<b>Maximum Limit</b>	Displays the maximum till balance that needs to be maintained for the <b>User ID</b> and currency combination.
<b>Current Till Balance</b>	Displays the current till balance based on the till cash position for the specified currency.
<b>Branch Breaching Limit</b>	Displays the values under this section.
<b>Branch Code</b>	Displays the code of the logged-in branch.
<b>Currency</b>	Displays the currency code.
<b>Minimum Limit</b>	Displays the minimum limit that needs to be maintained for the branch.

**Table 2-5 (Cont.) Branch Breach Limits - Field Description**

Field	Description
<b>Maximum Limit</b>	Displays the maximum limit that needs to be maintained for the branch.
<b>Current Total Balance</b>	Displays the branch total cash position, currency-wise.

## 2.6 Till Vault Position

The **Till Vault Position** screen is used to view the cash position of all the currencies at any time for the *Teller ID* or *Vault ID*, which is logged in for the current posting date. It also shows the denomination details.

To view the cash position of all the currencies:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Operations**, click **Till Vault Position** or specify **Till Vault Position** in the search icon bar and select the screen.

The **Till Vault Position** screen is displayed.

**Figure 2-6 Till Vault Position**

The screenshot shows the 'Till Vault Position' interface. At the top, there are input fields for 'Branch Code' (value: 006) and 'Branch Posting Date' (value: March 30, 2018). Below these is the 'Teller/Vault ID' field (value: REMOTLR14) and a 'Refresh' button. The main content is divided into two sections: 'Currency Details' and 'Denomination Details'. The 'Currency Details' table has columns for Currency, Opening Balance, Incoming Cash Amount, Outgoing Cash Amount, Total Cash, and Till/Vault Indicator. The 'Denomination Details' table has columns for Denomination Code, Denomination Value, Opening Balance, Incoming Cash Amount, Outgoing Cash Amount, Total Cash, and Units. Both tables show data for GBP.

Currency	Opening Balance	Incoming Cash Amount	Outgoing Cash Amount	Total Cash	Till/Vault Indicator
GBP	GBP 0.00	GBP 500.00	GBP 0.00	GBP 500.00	T

Denomination Code	Denomination Value	Opening Balance	Incoming Cash Amount	Outgoing Cash Amount	Total Cash	Units
1E	GBP 1.00	GBP 0.00	GBP 500.00	GBP 0.00	GBP 500.00	500

2. On the **Till Vault Position** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 2-6 Till Vault Position - Field Description**

Field	Description
<b>Branch Code</b>	Displays the logged-in branch.
<b>Branch Posting Date</b>	Displays the date on which the Till/Vault batch is opened.
<b>Teller/Vault ID</b>	Displays the logged-in Teller ID or Vault Teller ID.
<b>Currency Details</b>	Specify the fields under this section.
<b>Currency</b>	Displays the currency code.

**Table 2-6 (Cont.) Till Vault Position - Field Description**

Field	Description
<b>Opening Balance</b>	Displays the opening balance of the till or vault.
<b>Incoming Cash Amount</b>	Displays the incoming cash in the till or vault for the current posting date.
<b>Outgoing Cash Amount</b>	Displays the outgoing cash in the till or vault for the current posting date.
<b>Total Cash</b>	Displays the total cash available in the till or vault.
<b>Till Vault Indicator</b>	Displays whether the currency details apply to Till or Vault. ( <b>T</b> or <b>V</b> )
<b>Denomination Details</b>	Displays the denomination details under this section.
<b>Denomination Code</b>	Displays the denomination code maintained for the currency.
<b>Denomination Value</b>	Displays the denominations maintained for the currency.
<b>Opening Balance</b>	Displays the opening balance in the Till or vault in terms of denominations.
<b>Incoming Cash Amount</b>	Displays the incoming cash in the Till or vault in terms of denominations.
<b>Outgoing Cash Amount</b>	Displays the outgoing cash in the Till or vault in terms of denominations.
<b>Total Cash</b>	Displays the total cash currently available in the Till or vault for the day in terms of denominations.
<b>Units</b>	Displays the total units available for the specific denomination code.

## 2.7 Branch Total Position

The supervisor can use this screen to view the currency-wise cash position of all the Tellers and Vault Teller on the posting date for the logged-in branch.

To view the currency wise cash position:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Operations**, click **Branch Total Position** or specify **Branch Total Position** in the search icon bar and select the screen.

The **Branch Total Position** screen is displayed.


**Figure 2-7 Branch Total Position**

The screenshot shows the 'Branch Total Position' application window. It includes search filters for Branch Code (555), Posting Date (Mar 27, 2021), Currency, and Teller ID. There are radio buttons for 'All Till', 'All Vault', and 'All Till and Vault'. A 'Query' button is present. Below the filters is a table with columns: Currency, Teller ID, Opening Balance, Incoming Cash, Outgoing Cash, Closing Balance, and Till/Vault Indicator. The table currently displays 'No data to display.' and a pagination bar at the bottom shows 'Page 1 (0 of 0 Items)'.



- On the **Branch Total Position** screen, specify the fields. For more information on fields, refer to the field description table.

Table 2-7 Branch Total Position - Field Description

Field	Description
<b>Branch Code</b>	Displays the logged-in branch.
<b>Posting Date</b>	Indicates the date on which the teller totals position need to be enquired.  <div style="border: 1px solid #0070c0; padding: 5px; background-color: #e6f2ff;">  <b>Note:</b> By default, the system displays the current date. </div>
<b>Currency</b>	Displays the currency code for which the teller totals details needs to be displayed.
<b>Teller ID</b>	Displays the logged-in teller ID from the LOV.
<b>All Till</b>	Select this radio button to display all the open Teller Till details of the day.
<b>All Vault</b>	Select this radio button to display all the open Vault details of the day.
<b>All Till and Vault</b>	Select this radio button to display all the open Till and open Vault details of the day.
<b>Query</b>	Displays the details if you click this icon.
<b>Currency</b>	Displays the currency code for which the cash position is shown.
<b>Teller ID</b>	Displays the Teller ID for which the cash position is shown.
<b>Opening Balance</b>	Displays the opening balance of the Teller ID for the specific currency.
<b>Incoming Cash</b>	Displays the total incoming cash received in the Till.
<b>Outgoing Cash</b>	Displays the outgoing cash moved out of the Till.
<b>Closing Balance</b>	Displays the total amount pending in the Till.
<b>Till/Vault Indicator</b>	Displays the details of Till/Vault.

## 2.8 Close Teller Batch

The **Close Teller Batch** screen is used to close the teller batch for the given posting date.

The system allows closing the teller batch only when the below conditions are met:

- Verify that all the transactions are successfully processed to a logical end. If there are any pending transactions, the system prompts to either complete or reject the transaction.
- Verify that there is a difference between the physical cash and the cash calculated by the system. You need to book the overage or shortage accordingly, and then each Teller can close the teller batch for that day.

- Verify that the teller cash position retains the minimum limit for every currency as maintained in the User limits. If you breach the minimum limit, the system prompts the error to maintain the required minimum balance.



**Note:**

The teller batch can be opened and closed only once for the posting date.

To close the teller batch:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Operations**, click **Close Teller Batch** or specify **Close Teller Batch** in the search icon bar and select the screen.

The **Close Teller Batch** screen is displayed.



**Figure 2-8 Close Teller Batch**

2. On the **Close Teller Batch** screen, specify the details. For more information on fields, refer to the field description table.

**Table 2-8 Close Teller Batch - Field Description**

Field	Description
<b>Posting Date</b>	Indicates the date on which the teller batch needs to be closed.  <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;"> <p> <b>Note:</b> By default, the system displays the current date.</p> </div>
<b>Currency</b>	Displays the currency code in which the Teller deals.
<b>Total Cash</b>	Specify the total cash for a particular currency, physically present in the bank Teller, at the end of the current posting date.

Table 2-8 (Cont.) Close Teller Batch - Field Description

Field	Description
<b>Cash Available</b>	<p>Displays the system calculated cash for a particular currency, which is available in the teller at the end of the current posting date.</p> <p> <b>Note:</b></p> <p>The amount displayed in this column depends on the cash transactions that were carried out by the Teller until the last posting date.</p>
<b>Shortage/ Overage Amount</b>	<p>Displays the difference between the <b>Total Cash</b> and the <b>Cash Available</b>. Based on this difference, the overage or the shortage amount is displayed.</p> <p> <b>Note:</b></p> <p>An overage indicates that the physical cash with the Teller is more than the available cash as calculated by the system. A shortage indicates that the available cash calculated by the system is more than the physical cash present with the Teller.</p>
<b>Currency</b>	Displays the currency code.
<b>Denomination</b>	Displays the denomination code.
<b>Total Units</b>	Specify the total units available while closing the batch.
<b>Total Value</b>	Displays the total value based on the total units.
<b>System Units</b>	Displays the units available in the system.
<b>System Total</b>	Displays the total value available in the system.
<b>Shortage/Overage Units</b>	Displays the shortage/overage units.
<b>Shortage/Overage Amount</b>	Displays the shortage/overage amount.
<b>Total Cash Amount</b>	Displays the total cash amount.
<b>Denomination Total</b>	Displays the total denomination value with the currency.

3. Click **Submit**.

The cash balance is updated, and the teller batch is closed for the posting date.

 **Note:**

If there is any overage or shortage, the system displays an error message stating that the cash is not balanced for the Teller ID. Also, if any of the conditions mentioned above fail, the system displays an appropriate error message on submit.

## 2.9 Close Vault Batch

The **Close Vault Batch** screen is used to close the vault batch for a specific date.

The Vault Teller can log in and close the vault batch only if the below conditions are met:

- Verify if there is a difference in the physical cash and that calculated by the system, the overage or shortage has to be booked accordingly. After the overage or shortage is booked, the Vault Teller can close the vault batch for that day.
- Verify that the cash position of the Vault Teller retains the minimum limit for every currency as maintained in the User limits. If the minimum limit is breached, the system prompts the error to maintain the required minimum balance.

### Note:

The Vault Teller can close the vault batch even if the Tills are open. When the Vault Batch is closed, the user will not be able to post transactions like **Buy Cash from Vault** that involve Vault.

To close the vault batch:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Operations**, click **Close Vault Batch** or specify **Close Vault Batch** in the search icon bar and select the screen.

The **Close Vault Batch** screen is displayed.

**Figure 2-9 Close Vault Batch**

Servicing Transaction - Close Vault Batch TRN-0002308900034770, Branch Date - Mar 30, 2018

Close Vault Batch

Posting Date  
March 30, 2018

Currency	Total Cash	Cash Available	Shortage/Overage Amount
GBP	£0.00	£0.00	



Currency	Denomination	Total Units	Total Value	System Units	System Total	Shortage/Overage Units	Shortage/Overage Amount
No data to display.							

Total Cash Amount  Denomination Total

Cancel Submit Clear

2. On the **Close Vault Batch** screen, specify the fields. For more information on fields, refer to the field description table.

Table 2-9 Close Vault Batch - Field Description

Field	Description
<b>Posting Date</b>	Indicates the date on which the vault batch needs to be closed.   <b>Note:</b> By default, the system displays the current date.
<b>Currency</b>	Displays the currency code in which the Vault Teller deals.
<b>Total Cash</b>	Specify the total cash for a particular currency, physically present in the bank Vault Teller, at the end of the current posting date.
<b>Cash Available</b>	Displays the system calculated cash for a particular currency, which is available in the Vault Teller at the end of the current posting date.   <b>Note:</b> The amount displayed in this column depends on the cash transactions that were carried out by the Teller until the last posting date.
<b>Shortage/Overage Amount</b>	Displays the difference between the total cash and the cash available in the Vault, at the end of the current posting date.
<b>Currency</b>	Displays the currency code.
<b>Denomination</b>	Displays the denomination code.
<b>Total Units</b>	Specify the total units available while closing the batch.
<b>Total Value</b>	Displays the total value based on the total units.
<b>System Units</b>	Displays the units available in the system.
<b>System Total</b>	Displays the total value available in the system.
<b>Shortage/Overage Units</b>	Displays the shortage/overage units.
<b>Shortage/Overage Amount</b>	Displays the shortage/overage amount.
<b>Total Cash Amount</b>	Displays the total cash amount.
<b>Denomination Total</b>	Displays the total denomination value with the currency.

3. Click **Submit**.

The cash balance is updated and the vault batch is closed for the posting date.

 **Note:**

During vault batch closure, the system will internally transfer the closing balance from the current open Vault ID to the Primary vault of the branch. If there is any overage or shortage, the system displays an error message stating that the cash is not balanced for the Teller ID. Also, if any of the conditions mentioned above fail, the system displays an appropriate error on submit.

## 2.10 Close Branch Batch

The **Close Branch Batch** screen is used to close the branch batch after confirming that all the branch transactions have been accounted for in the account books.


The posting date for closing a branch batch must be the same date on which the respective branch batch was opened. You need to close all the teller batches and the vault batch of the branch before closing the branch batch for that posting date. Archiving is done as a part of **Close Branch Batch** as per the archival days set up for the branch.

To close the branch batch:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Operations**, click **Close Branch Batch** or specify **Close Branch Batch** in the search icon bar and select the screen.


The **Close Branch Batch** screen is displayed.

**Figure 2-10 Close Branch Batch**



2. On the **Close Branch Batch** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 2-10 Close Branch Batch - Field Description**

Field	Description
<b>Posting Date</b>	Indicates the date on which the branch batch needs to be closed.  <div style="border: 1px solid #0070c0; background-color: #e6f2ff; padding: 5px;"> <p> <b>Note:</b> By default, the system displays the current date.</p> </div>

3. Click **Submit**.

The branch batch is closed for the specified posting date.

## 2.11 Book Shortage


The Teller or Vault Teller can use the **Book Shortage** screen to book the shortage if the actual or physical cash present is less than the system cash.

While booking the shortage, the system lowers the cash balance to bring it in sync with the physical cash balance of the Teller by sending the difference to a cash shortage GL. Once the system cash and the physical cash are synchronized, the Teller can perform the cash balancing and close the Teller/Vault Teller batch for the posting date.

To book the shortage:


1. On the **Home** screen, from **Teller** mega menu, under **Till-Vault Operations**, click **Book Shortage** or specify **Book Shortage** in the search icon bar and select the screen.

The **Book Shortage** screen is displayed.

**Figure 2-11 Book Shortage**


2. On the **Book Shortage** screen, specify the fields. For more information on fields, refer to the field description table.

Table 2-11 Book Shortage - Field Description

Field	Description
Transaction Amount	<p>Displays the local currency of the branch. Specify the amount that needs to be booked for the shortage.</p> <div style="border: 1px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b> The user can select another currency from the drop-down values in which the shortage amount is to be booked.</p> </div>
Narrative	Displays the default narrative Book Shortage and it can be modified.

3. Specify the denomination details. For information on the fields in the **Denomination** segment, refer to [Add Denomination Details](#).
4. Click **Submit**.

A teller sequence number is generated and the Transaction Completed Successfully information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any warning raised when the transaction saves. On transaction completion, the system reduces the cash balance by this transaction amount to synchronize with physical cash held with Teller.

- [Add Denomination Details](#)  
The **Denomination** segment is used to view the denominations maintained for the transaction currency and enter the denomination units.

## 2.11.1 Add Denomination Details

The **Denomination** segment is used to view the denominations maintained for the transaction currency and enter the denomination units.

Make sure that the main transaction details are added to the transaction screen.

The denomination details for the withdrawal transactions (when cash is disbursed to the customer) will be populated automatically based on the cash availability in the Teller's Till.



**Figure 2-12 Denomination Details**

▼ **Denomination**

Bills			Coins		
Denom Code ▾	Units ▾	Value ▾	Denom Code ▾	Units ▾	Value ▾
No data to display.			No data to display.		

Total Cash Amount



Denomination Amount

Validate the denomination details. For more information on fields, refer to the field description table.

**Table 2-12 Denomination Details - Field Description**

Field	Description
<b>Denom Code</b>	Displays the unique denomination codes for each currency.
<b>Units</b>	<p>Indicates the number of units for the specified denomination.</p> <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>By default, the till contents are incremented for inflow transactions such as cash deposits and decremented for outflow transactions such as cash withdrawal. To reverse the transaction, you can specify units in negative.</p> </div>
<b>Value</b>	<p>Displays the system-computed face value of the denomination based on the number of units.</p> <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>For example, if the denomination code represents USD 100 and the unit is specified as 3, the value will be displayed as 300.</p> </div>

Table 2-12 (Cont.) Denomination Details - Field Description

Field	Description
<b>Denomination Amount</b>	<p>Displays the system-computed value of the denomination by multiplying the denomination value with the number of units.</p> <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>For example, if the denomination code represents USD 100 and the number of units is 10, the denomination amount will be 1000.</p> </div>
<b>Total Cash Amount</b>	<p>Displays the total cash amount.</p> <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>The system computes the Denomination Amount and validates the amount if it is equal to the Total Cash Amount. It also prompts an error during saving if there is any difference.</p> </div>

## 2.12 Book Overage

The Teller or Vault Teller can use this screen to book the physical cash held in a particular currency, which exceeds the cash in that currency shown in the system.

While booking a cash overage, the system passes the difference to a cash overage liability GL and increases the cash balance, and brings it to synchronize with the physical balance with the Teller. Once the system cash and the physical cash are synchronized, the Teller can perform cash balancing and close the Teller/Vault Teller batch for the posting date.

To book the overage:


1. On the **Home** screen, from **Teller** mega menu, under **Till-Vault Operations**, click **Book Overage** or specify **Book Overage** in the search icon bar and select the screen.

The **Book Overage** screen is displayed.

**Figure 2-13 Book Overage**

2. On the **Book Overage** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 2-13 Book Overage - Field Description**

Field	Description
<b>Transaction Amount</b>	<p>Displays the local currency of the branch. Specify the amount that needs to be booked for the overage.</p> <div style="border: 1px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b></p> <p>The user can select another currency from the drop-down values in which the shortage amount is to be booked.</p> </div>
<b>Narrative</b>	<p>Displays the default narrative <code>Book Overage</code> and it can be modified.</p>

3. Specify the denomination details. For information on the fields in the **Denomination Details** segment, refer to [Add Denomination Details](#).
4. Click **Submit**.

A teller sequence number is generated, and the `Transaction Completed Successfully` information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any warning raised when the transaction saves. On transaction completion, the system increases the cash balance by this transaction amount to synchronize with physical cash held with Teller.

# 3

## Transfers

The Teller can use Transfers to perform inter-bank transfers, intra-bank transfers, and cross-border transactions.

This topic contains the following subtopics:

- [Account Transfer](#)  
The **Account Transfer** screen is used to transfer funds from one account to another account within the bank.
- [In-House Check Deposit](#)  
The **In House Check Deposit** screen is used to capture in-house check deposit transactions for the customers.

### 3.1 Account Transfer

The **Account Transfer** screen is used to transfer funds from one account to another account within the bank.

The funding account and beneficiary account can be in different currencies and belong to different branches.

To perform account transfer:

1. On the **Home** screen, from **Teller** mega menu, under **Transfers**, click **Account Transfer** or specify **Account Transfer** in the search icon bar and select the screen.



The **Account Transfer** screen is displayed.

**Figure 3-1 Account Transfer**

The screenshot shows the 'Account Transfer' screen. The top bar includes the title 'Servicing Transaction - Account Transfer', a 'Customer Search' icon, and the transaction ID 'TRN-0012402500036050, Branch Date - Jan 25, 2022'. The main content area is divided into three columns. The left column, titled 'Account Transfer', contains several input fields: 'Debit Account' (with a dropdown arrow), 'Debit Amount' (with a dropdown arrow), 'Credit Account', 'Credit Account Name', 'Credit Account Branch', 'Exchange Rate', and 'Narrative'. The right column, titled 'Memo Alerts', shows a green box with the text 'No Data to Display'. Below this is a section for 'Frequent Customer Operations'. At the bottom right of the screen are three buttons: 'Cancel', 'Submit', and 'Clear'.

2. On the **Account Transfer** screen, specify the fields. For more information on fields, refer to the field description table.

Table 3-1 Account Transfer - Field Description

Field	Description
<b>Debit Account</b>	Specify the customer account from which the funds need to be debited.
<b>Debit Amount</b>	Displays the transaction account currency. Specify the transaction amount that needs to be debited from the customer account.
<b>Credit Account</b>	Specify the account to which the funds need to be credited.
<b>Credit Account Name</b>	Displays the description of the account number specified.
<b>Credit Account Branch</b>	Displays the branch code of the account number specified.
<b>Credit Amount</b>	Displays the amount in terms of the credit account currency.  <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 10px; background-color: #E6F2FF;"> <p> <b>Note:</b></p> <p>This field is displayed only if <i>Multi-Currency Configuration</i> at the <i>Function Code Indicator</i> level is set as <i>Y</i>.</p> </div>
<b>Exchange Rate</b>	Displays the exchange rate used to convert the transaction account currency into credit account currency and it can be modified.  <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 10px; background-color: #E6F2FF;"> <p> <b>Note:</b></p> <p>If the transaction currency is the same as the account currency, the system displays the exchange rate as 1. This field is displayed only if <i>Multi-Currency Configuration</i> at the <i>Function Code Indicator</i> level is set as <i>Y</i>.</p> </div>
<b>Narrative</b>	Displays the default narrative as <b>Account Transfer</b> , and it can be modified.

3. Specify the charge details. For information on the fields in the **Charge Details** segment, refer to [Charge Details](#).
4. Click **Submit**.

A teller sequence number is generated, and the *Transaction Completed Successfully* information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any warning raised when the transaction saves.

When you submit, the transaction details are handed off to accounting.

## 3.2 In-House Check Deposit

The **In House Check Deposit** screen is used to capture in-house check deposit transactions for the customers.

To capture in-house check deposit transactions:

1. On the **Home** screen, from **Teller** mega menu, under **Transfers**, click **In House Check Deposit** or specify **In House Check Deposit** in the search icon bar and select the screen.

The **In House Check Deposit** screen is displayed.





**Figure 3-2 In House Check Deposit**

2. On the **In House Check Deposit** screen, specify the fields. For more information on fields, refer to the field description table.


**Table 3-2 In House Check Deposit - Field Description**

Field	Description
<b>Debit Account</b>	Specify the account number of the drawer.
<b>Debit Account Name</b>	Displays the name of the account.
<b>Debit Account Branch</b>	Displays the branch code of the account number specified.
<b>Check Amount</b>	Specify the currency and amount as mentioned in the check.

**Table 3-2 (Cont.) In House Check Deposit - Field Description**


Field	Description
<b>Check Number</b>	Specify the check number.  <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;">  <b>Note:</b>               The system validates the status of the check and prompts an error message if in case of a Used or Stopped or Invalid check.           </div>
<b>Check Date</b>	Specify the date of issue as mentioned in the check.
<b>Credit Account</b>	Specify the account number that needs to be credited with the check amount.
<b>Credit Amount</b>	Displays the transaction amount based on the exchange rate.  <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;">  <b>Note:</b>               This field is displayed only if Multi-Currency Configuration at Function Code Indicator level is set as Y.           </div>
<b>Exchange Rate</b>	Displays the exchange rate used to convert the transaction currency into account currency and it can be modified.  <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;">  <b>Note:</b>               If the transaction currency is the same as the account currency, the system displays the exchange rate as 1. This field is displayed only if Multi-Currency Configuration at Function Code Indicator level is set as Y.           </div>
<b>Total Charges (LCY)</b>	Displays the total charge amount, which is computed by the system.  <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;">  <b>Note:</b>               This field is displayed only if Total Charges Configuration at Function Code Indicator level is set as Y.           </div>

**Table 3-2 (Cont.) In House Check Deposit - Field Description**

Field	Description
<b>Reject Code</b>	<p>Select the reject code from the list of values, which are maintained in the <b>Reject Code Maintenance</b> screen.</p> <div style="border: 1px solid #0070C0; padding: 10px; background-color: #E6F2FF;"> <p> <b>Note:</b></p> <p>If the in house check deposit transaction needs to be rejected, you can reject it by specifying the appropriate reject code in this field. The transaction can be rejected for any of the following reasons:</p> <ul style="list-style-type: none"> <li>• Insufficient funds</li> <li>• Signature mismatch</li> <li>• Stale check</li> </ul> </div>
<b>Reject Code Description</b>	Displays the description of the specified reject code.
<b>Narrative</b>	Displays the default narrative as <b>In-House Check Deposit</b> , and it can be modified.

3. Specify the charge details. For information on the fields in the **Charge Details** segment, refer to [Charge Details](#).
4. Click **Submit**.

A teller sequence number is generated, and the `Transaction Completed Successfully` information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any warning raised when the transaction saves.

When you submit, the transaction details are handed off to accounting.



# 4

## Journal Log

The Teller or Supervisor can use screens under the **Journal Log** menu to view the status of transactions performed by them. It is also used to resubmit or reject an incomplete transaction or reverse a completed transaction.

This topic contains the following subtopics:

- [About Electronic and Servicing Journals](#)  
In the **Electronic Journal** and **Servicing Journal** screens, Tellers can view the status of the transactions performed only by them and Supervisors can view the status of the transactions performed by them and other Tellers.
- [Electronic Journal](#)  
Tellers and Supervisors can use the **Electronic Journal** screen to view the status of the cash transactions performed by them on the posting date.
- [Servicing Journal](#)  
Tellers and Supervisors can use this screen to view the status of the non-cash transactions performed by them on the posting date.
- [Reassign Transactions](#)  
Tellers and Supervisors can use the **Reassign Transactions** screen to re-assign the transactions that are pending approval to the other Supervisor or to unlock a locked transaction.

### 4.1 About Electronic and Servicing Journals

In the **Electronic Journal** and **Servicing Journal** screens, Tellers can view the status of the transactions performed only by them and Supervisors can view the status of the transactions performed by them and other Tellers.


#### Common Operations

These screens are used to perform the following operations:

**Table 4-1 Operations in Journal Log**

Operation	Description
<b>View Status</b>	View the status of all transactions performed by the logged-in Teller ID.

Table 4-1 (Cont.) Operations in Journal Log

Operation	Description
<b>Reverse Completed Transactions</b>	<p>Reverse the completed transaction posted by Teller during the day and the previous day. The following conditions apply for the reversal of both current and previous day transactions:</p> <ul style="list-style-type: none"> <li>• If the reversal of a transaction is performed within the purge days configured.</li> <li>• If the reversal allowed flag is enabled at the function indicator level for the function code.</li> </ul> <div style="border: 1px solid #0070C0; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <ul style="list-style-type: none"> <li>• During the reversal of both cash and non-cash transactions, the transaction date will be the date on which reversal is initiated and accounting will be handed off with the transaction date.</li> <li>• During the reversal of cash transactions, till update will be done on the date of reversal for the respective teller ID who has initiated the reversal from the journal log.</li> </ul> </div>
<b>Re-submit Incomplete Transactions</b>	<p>Re-submit the incomplete transactions performed by the logged-in Teller ID, that are either:</p> <ul style="list-style-type: none"> <li>• Approved by the supervisor and moved to Teller EJ log for re-submission.</li> <li>• Processed by an external system and responded to Teller with the status as <b>Success</b>.</li> </ul>
<b>Reject Incomplete Transactions</b>	<p>Reject the incomplete transactions that are either:</p> <ul style="list-style-type: none"> <li>• Rejected by an external system with the status as <b>Reject</b>.</li> <li>• Prompted with error due to processing validations.</li> </ul>
<b>View Approval History</b>	<p>View the approval history to see the list of all transactions that are either approved or rejected by the logged-in approver ID.</p>
<b>Approve or Reject Transactions</b>	<p>Approve or Reject the transactions that are assigned to the logged-in Approver ID during the day.</p>
<b>Discard of Reversal Transactions</b>	<p>When the approver rejects the reversal request, the transaction is marked as rejected and the teller discards the rejected status, the transaction is moved to the discarded transaction.</p>

In the tile and grid views, the transactions are displayed for all statuses by default. The status can be changed using the filters option. If the user closes the screen with a

status other than All, the selected status will default until the browser tab is closed. The following conditions apply for the default status:

**Table 4-2 Conditions for Default Status**

Condition	Description
The browser tab is not closed	The transactions will be displayed for the previously selected status if the screen is launched again.
The browser tab is closed and the user logs in to the application in a new tab or window	The transactions will be displayed for all statuses if the screen is launched.

### Common Icons, Actions, and Shortcut Keys

Users can perform one of the following actions on the **Electronic Journal** and **Servicing Journal** screens:

**Table 4-3 Symbols**

Icon	Description
<b>Tile View</b> icon	Click on this icon to display the details in the tile view.
<b>Grid View</b> icon	Click on this icon to display the details in the grid view.

After filling the necessary fields in the **Electronic Journal** and **Servicing Journal** screens, you can do one of the following steps:

**Table 4-4 Basic Actions**

Action	Description
<b>Fetch</b>	Click <b>Fetch</b> to get the list of transactions based on the query criteria specified. When you click <b>Fetch</b> , the following details are displayed for each transaction: <ul style="list-style-type: none"> <li>• Function Code and Screen Name</li> <li>• Transaction Reference Number</li> <li>• Teller Sequence Number</li> <li>• Transaction Amount</li> <li>• Account Number</li> <li>• Teller ID</li> <li>• Teller Remarks</li> </ul>
<b>Clear</b>	Click <b>Clear</b> to clear the specified values.

Users can also navigate to necessary the transaction; perform the operations using the shortcut keys as follows:

1. Press the **Tab** key, and navigate to the list of transactions in grid view.
2. Use **Up/Down** arrow keys to select the necessary transaction.
3. Use **Left/Right** arrow keys to select the icon.
4. Press **Spacebar** to view the operations applicable to the selected transaction.
5. Use **Up/Down** arrow keys to select the necessary operation.

## 4.2 Electronic Journal

Tellers and Supervisors can use the **Electronic Journal** screen to view the status of the cash transactions performed by them on the posting date.


For information on the common operations and icons on this screen, refer to [About Electronic and Servicing Journals](#).

To view the status of the cash transactions:

1. On the **Home** screen, from **Teller** mega menu, under **Journal Log**, click **Electronic Journal** or specify **Electronic Journal** in the search icon bar and select the screen.

The **Electronic Journal** screen is displayed.

**Figure 4-1 Electronic Journal (List View)**




You can perform any of the following actions in this screen:

- Click **Transaction Info** icon to view the transaction information. This screen provides the details of the transactions handed off to the external system.

The **Transaction Info** pop-up screen is displayed.

**Figure 4-2 Transaction Info**



- Click **View Transaction** icon to view the transaction details. The following details are displayed based on the transaction status in the filters:
  - Teller Sequence
  - Transaction Reference

- Transaction Status
  - Time Resubmitted
  - Time Stamp/Approval Time Stamp
  - Supervisor ID
  - Supervisor Remarks
  - Override Info
    - Click **Override Info** icon to view the details for approval flow request.
- Click **Submit Transaction** icon to submit the transaction.
  - Click **Discard Transaction** icon to discard the transaction.
  - Click **Reverse Transaction** icon to reverse the transaction.

**Figure 4-3 Electronic Journal (Grid View)**

Function Code	Transaction Reference	Teller Sequence	Transaction Currency	Transaction Amount	Account Number	Teller ID	Teller Remarks	Transaction Status	Action
1013- Cheque Withdrawal	0062308900033961	1	GBP	100	000000155	REMOTLR12	No Comments	Completed	...
1460- Miscellaneous GL Credit	0062308900033758	MGD-1	GBP	1000	GL00000001	REMOTLR12	No Comments	Completed	...
1460- Miscellaneous GL Credit	0062308900033757	MGD-1	GBP	8500	GL00000001	REMOTLR12	No Comments	Completed	...
1401- Cash Deposit	0062308900033740	1	GBP	122	000000105	REMOTLR12	No Comments	Completed	...
1401- Cash Deposit	0062308900033725	1	GBP	100	000000105	REMOTLR12	No Comments	Completed	...
1401- Cash Deposit	0062308900033619	3	GBP	1000	000000105	REMOTLR12	No Comments	Completed	...
1001- Cash Withdrawal	0062308900033617	2	GBP	5	000000105	REMOTLR12	No Comments	Completed	...
1001- Cash Withdrawal	0062308900033615	1	GBP	100	000000105	REMOTLR12	No Comments	Completed	...
1401- Cash Deposit	0062308900033612	3	GBP	100	000000105	REMOTLR12	No Comments	Sent Back	...
7551- Book Shortage	0062308900033305	NA	GBP	100		REMOTLR12	No Comments	Completed	...

2. Click **Filter** icon to filter the results on the tile/grid view based on the search criteria. The **Filters** pop-up screen is displayed.




**Figure 4-4 Filters (Electronic Journal)**

3. On the **Filters** pop-up screen, specify the details fetch the records. For more information on fields, refer to the field description table.

**Table 4-5 Filters - Field Description**

Field	Description
<b>Teller ID</b>	Specify the Teller ID.  <b>Note:</b> You can also click the search icon and select the Teller ID from the list of values.
<b>Function Code</b>	Specify the function code for which the inquiry is to be made.  <b>Note:</b> You can also click the search icon and select the Teller ID from the list of values.

Table 4-5 (Cont.) Filters - Field Description

Field	Description
<b>Branch Posting Date</b>	Specify the branch posting date for which the inquiry is to be made.   <b>Note:</b> By default, the current posting date is displayed.
<b>Account Number</b>	Specify the account number.   <b>Note:</b> You can also click the search icon and select the Teller ID from the list of maintained account numbers.
<b>Teller Sequence Prefix</b>	Click the search icon and select from the list of values.
<b>Transaction Status</b>	Select the transaction status from the drop-down values.   <b>Note:</b> By default, <b>All</b> status is selected.
<b>Transaction Reference</b>	Specify the transaction reference number.
<b>From Sequence Number</b>	Specify the start number of the sequence range.
<b>To Sequence Number</b>	Specify the end number of the sequence range.
<b>From Transaction Time</b>	Specify the transaction start time.
<b>To Transaction Time</b>	Specify the transaction end time.
<b>From Amount Range</b>	Specify the “from” amount of the amount range.
<b>To Amount Range</b>	Specify the “to” amount of the amount range.
<b>Transaction Currency</b>	Click the search icon and select the transaction currency from the list of values.

## 4.3 Servicing Journal

Tellers and Supervisors can use this screen to view the status of the non-cash transactions performed by them on the posting date.


For information on the common operations and icons on this screen, refer to [About Electronic and Servicing Journals](#).

To view the status of the non-cash transactions:

1. On the **Home** screen, from **Teller** mega menu, under **Journal Log**, click **Servicing Journal** or specify **Servicing Journal** in the search icon bar and select the screen.

The **Servicing Journal** screen is displayed.

**Figure 4-5 Servicing Journal (Tile View)**




You can perform any of the following actions in this screen:

- Click **Transaction Info** icon to view the transaction information. This screen provides the details of the transactions handed off to the external system.

The **Transaction Info** pop-up screen is displayed.

**Figure 4-6 Transaction Info**



- Click **View Transaction** icon to view the transaction details. The following details are displayed based on the transaction status in the filters:
  - Teller Sequence
  - Transaction Reference
  - Transaction Status
  - Time Resubmitted
  - Time Stamp/Approval Time Stamp
  - Supervisor ID
  - Supervisor Remarks
  - Override Info
- Click **Override Info** icon to view the details for approval flow request.



- Click **Submit Transaction** icon to submit the transaction.
- Click **Discard Transaction** icon to discard the transaction.
- Click **Reverse Transaction** icon to reverse the transaction.

**Figure 4-7 Servicing Journal (Grid View)**

Function Code	Transaction Reference	Teller Sequence	Transaction Currency	Transaction Amount	Account Number	Teller ID	Teller Remarks	Transaction Status	Action
1005- Miscellaneous GL Transfer	0012302500034120	11	GBP	100	3134000007	KEERTHI	No Comments	Completed	...
1408- Miscellaneous Customer Credit	0012302500034119	10	GBP	100	E011111139	KEERTHI	No Comments	Completed	...
0006- Account Transfer	0012302500034116	AT-29	GBP	100	E011111139	KEERTHS	No Comments	Completed	...
9001- Open Teller Batch	0012302500034097	6				KEERTHI	No Comments	Completed	...
0006- Account Transfer	0012302500033772	AT-18	GBP	100	E011111139	SAJOSH	No Comments	Completed	...
0006- Account Transfer	0012302500033771	AT-17	GBP	100	E011111141	SAJOSH	No Comments	Completed	...
0006- Account Transfer	0012302500033770	AT-16	GBP	100	E011111139	SAJOSH	No Comments	Completed	...
0006- Account Transfer	0012302500033768	AT-15	GBP	100	E011111139	SAJOSH	No Comments	Completed	...
9002- Close Teller Batch	0012302500033728	16				KEERTHS	No Comments	Completed	...
9001- Open Teller Batch	0012302500033712	17				KEERTHS	No Comments	Completed	...

Page 1 of 1 (1-10 of 10 items) | < 1 >

2. Click the **Filter** icon to filter the results on the tile/grid view based on the search criteria. The **Filters** pop-up screen is displayed.

**Figure 4-8 Filters (Servicing Journal)**

### Filter

**Teller ID**

**Function Code**

**Branch Posting Date**

**Account Number**

**Teller Sequence Prefix**

**Transaction Status**

**Transaction Reference**

**Sequence Number**

**To Sequence N**

**Transaction Time**

**To Transaction Time**

**Amount Range**

**To Amount Range**

**Transaction Currency**

- On the **Filters** pop-up screen, specify the details fetch the records. For more information on fields, refer to the field description table.

Table 4-6 Filters - Field Description






Field	Description
<b>Teller ID</b>	Specify the Teller ID.   <b>Note:</b> You can also click the search icon and select the Teller ID from the list of values.
<b>Function Code</b>	Specify the function code for which the inquiry is to be made.   <b>Note:</b> You can also click the search icon and select the Teller ID from the list of values.
<b>Branch Posting Date</b>	Specify the branch posting date for which the inquiry is to be made.   <b>Note:</b> By default, the current posting date is displayed.
<b>Account Number</b>	Specify the account number.   <b>Note:</b> You can also click the search icon and select the Teller ID from the list of maintained account numbers.
<b>Teller Sequence Prefix</b>	Click the search icon and select from the list of values.
<b>Transaction Status</b>	Select the transaction status from the drop-down values.   <b>Note:</b> By default, <b>All</b> status is selected.
<b>Transaction Reference</b>	Specify the transaction reference number.

Table 4-6 (Cont.) Filters - Field Description

Field	Description
<b>From Sequence Number</b>	Specify the start number of the sequence range.
<b>To Sequence Number</b>	Specify the end number of the sequence range.
<b>From Transaction Time</b>	Specify the transaction start time.
<b>To Transaction Time</b>	Specify the transaction end time.
<b>From Amount Range</b>	Specify the “from” amount of the amount range.
<b>To Amount Range</b>	Specify the “to” amount of the amount range.
<b>Transaction Currency</b>	Click the search icon and select the transaction currency from the list of values.

## 4.4 Reassign Transactions


Tellers and Supervisors can use the **Reassign Transactions** screen to re-assign the transactions that are pending approval to the other Supervisor or to unlock a locked transaction.

To reassign the Supervisor ID:

1. On the **Home** screen, from **Teller** mega menu, under **Journal Log**, click **Reassign Transactions** or specify **Reassign Transactions** in the search icon bar and select the screen.




The **Reassign Transactions** screen is displayed.

Figure 4-9 Reassign Transactions



2. On the **Reassign Transactions** screen, specify the details fetch the records. For more information on fields, refer to the field description table.

Table 4-7 Reassign Transactions - Field Description

Field	Description
<b>Branch Posting Date</b>	Specify the branch posting date for which the inquiry is to be made.   <b>Note:</b> By default, the current posting date is displayed.
<b>Teller ID</b>	Select the Teller ID from the list of values.
<b>Function Code</b>	Specify the function code for which the inquiry is to be made.   <b>Note:</b> You can also click the search icon and select from the list of the maintained function codes.
<b>Account Number</b>	Specify the account number.   <b>Note:</b> The LOV fetches a list of the maintained account numbers.
<b>Teller Sequence Prefix</b>	Select from the list of values.
<b>From Sequence Number</b>	Specify the start number of the sequence range.
<b>To Sequence Number</b>	Specify the end number of the sequence range.
<b>From Transaction Time</b>	Specify the transaction start time.
<b>To Transaction Time</b>	Specify the transaction end time.
<b>From Amount Range</b>	Specify the “from” amount of the amount range.
<b>To Amount Range</b>	Specify the “to” amount of the amount range.
<b>Journal Log Type</b>	Select the type from the drop-down values ( <b>Electronic Journal</b> or <b>Servicing Journal</b> ).


- After you specify the necessary fields, you can perform one of the following actions:

**Table 4-8 Basic Actions**

Action	Description
<b>Fetch</b>	Click <b>Fetch</b> to get the list of transactions based on the query criteria specified. When you click <b>Fetch</b> , the following details are displayed for each transaction: <ul style="list-style-type: none"> <li>• Function Code and Screen Name</li> <li>• Transaction Reference Number</li> <li>• Teller Sequence Number</li> <li>• Transaction Amount</li> <li>• Account Number</li> <li>• Teller ID</li> <li>• Supervisor ID</li> <li>• Teller Remarks</li> <li>• Supervisor Remarks</li> </ul>
<b>Clear</b>	Click <b>Clear</b> to clear the transaction list.

The transactions fetched based on the search criteria are displayed in Tile View. In the Tile View, you can click the necessary icons to perform the operations.

**Figure 4-10 List of Transactions**



In the transaction record, you can perform one of the following operations:

**Table 4-9 Actions for Transaction Record**

Action	Description
<b>Unlock icon</b>	Click on this icon to unlock the transaction.
<b>Reassign icon</b>	Click on this icon to reassign the Supervisor ID for the transaction.

# 5

## Customer Transactions

The Teller can use Customer Transactions to perform financial transactions for customer accounts.

This topic contains the following subtopics:

- [Cash Deposit](#)  
The **Cash Deposit** screen is used to deposit the cash in a CASA. Cash can be deposited in either account currency or any foreign currency that is allowed.
- [Cash Withdrawal](#)  
The **Cash Withdrawal** screen is used to withdraw funds from the CASA account of the customer.
- [Check Withdrawal](#)  
The **Check Withdrawal** screen is used to withdraw cash from the CASA account of the customer against the in-house check.
- [FX Sale Against Account](#)  
The Foreign Exchange (**FX**) **Sale Against Account** screen is used to sell the foreign currency from the branch through the CASA account.
- [FX Sale Against Walk-in](#)  
The **FX Sale Against Walk-in** screen is used to sell a foreign currency to a walk-in customer in return for the equivalent amount received in any other currency.
- [FX Purchase Against Account](#)  
The **FX Purchase Against Account** screen is used to purchase foreign currency from the branch through the CASA account.
- [FX Purchase Against Walk-in](#)  
The **FX Purchase Against Walk-in** screen is used to buy a foreign currency from a walk-in customer in return for the equivalent amount in any other currency.

### 5.1 Cash Deposit

The **Cash Deposit** screen is used to deposit the cash in a CASA. Cash can be deposited in either account currency or any foreign currency that is allowed.

Whenever any transaction in foreign currency is posted to the account, it is converted to the account currency based on the maintained exchange rate for the transaction.

To deposit cash:

1. On the **Home** screen, click **Teller**. On the Teller Mega Menu, under **Customer Transaction**, click **Cash Deposit** or specify the **Cash Deposit** in the search icon bar.  
The **Cash Deposit** screen is displayed.

Figure 5-1 Cash Deposit

2. On the **Cash Deposit** screen, specify the fields. For more information on fields, refer to the field description table.

Table 5-1 Cash Deposit - Field Description






Field	Description
<b>Account Number</b>	<p>Specify a valid account number for the customer. When you press the <b>Tab</b> key, the corresponding account information will be displayed in the <b>Customer Information</b> widget.</p> <p> <b>Note:</b></p> <p>The system displays an override or error message on the tab out of Account Number based on the account dormancy parameters.</p>
<b>Transaction Amount</b>	<p>Displays the local currency of the branch. You can also select other transaction currencies from the drop-down values. Specify the transaction amount that needs to be credited to the customer account.</p>
<b>Exchange Rate</b>	<p>Displays the exchange rate used to convert the transaction currency into account currency and it can be modified.</p> <p> <b>Note:</b></p> <p>If the transaction currency is the same as the account currency, the system displays the exchange rate as 1. This field is displayed only if <b>Multi-Currency Configuration</b> at <b>Function Code Indicator</b> level is set as <b>Y</b>.</p>

Table 5-1 (Cont.) Cash Deposit - Field Description

Field	Description
<b>Negotiated Exchange Rate</b>	Specify the negotiated exchange rate that should be used for foreign currency transactions between the treasury and the branch. You need to specify the negotiated exchange rate only when the currencies involved in the transaction are different.   <b>Note:</b>  This field is applicable only if the transaction involves cross currency and only if cross currency enabled and <code>Negotiated_Rate_Enabled</code> Configuration at Function Code Indicator level is set as Y.
<b>Negotiated Reference Number</b>	Specify the unique reference number that should be used for negotiation of cost rate, in foreign currency transaction. If you have specified the negotiated cost rate, then you need to specify the negotiated reference number also.
<b>Account Amount</b>	Displays the transaction amount converted in terms of account amount based on the exchange rate.   <b>Note:</b>  This field is displayed only if <code>Multi-Currency Configuration</code> at Function Code Indicator level is set as Y.
<b>Total Charge Amount</b>	Displays the total charge amount, which is computed by the system in the local currency of the branch.   <b>Note:</b>  This field is displayed only if <code>Total Charges Configuration</code> at Function Code Indicator level is set as Y.
<b>Narrative</b>	Displays the default narrative as <b>Cash Deposit</b> , and it can be modified.

3. Specify the charge details. For information on the fields in the **Charge Details** segment, refer to [Charge Details](#).
4. Specify the denomination details. For information on the fields in the **Denomination Details** segment, refer to [Add Denomination Details](#).
5. Click **Submit**.

Once you submit the transaction, the system validates the following:



- Mandatory fields
- Allowed minimum/maximum limit amount for the user ID
- Allowed currency for Teller user ID
- Till balance and branch breaching limit
- Function code preferences

If any of the validation fails, the system will prompt appropriate information, warning, or error message. For more information, refer to the following steps:

- If an information message is prompted, click **OK** to confirm and complete the transaction.
- If a warning message is prompted, the system will move the transaction for authorization. Once approved, the transaction is moved to Teller **Electronic Journal** for completion. Refer to authorization procedures to know more about authorization processing.
- If any validation error is prompted, you need to update the details to fix the error and re-submit the transaction.
- If any other error message is prompted, the transaction is discarded and does not get saved.
- If you click **Close** or **Cancel** after specifying the transaction details, then the data will not persist.

When the Teller completes the transaction, the corresponding Teller's cash position is updated.

The `Transaction Completed Successfully` information message is displayed.

- [Charge Details](#)  
The **Charge Details** segment is used to view the computed charge details based on the charge maintenance defined for the function code.


## 5.1.1 Charge Details

The **Charge Details** segment is used to view the computed charge details based on the charge maintenance defined for the function code.

Make sure that the charge details data segment are added to the transaction screen.

This segment is applicable for all Financial Customer transactions. If no charge is maintained for the combination, then the transaction is saved without any charges.


**Figure 5-2 Charge Details**




Charge Code	Currency	Charge Amount	Waiver	Charge By Cash
No data to display.				

You can view or waive the computed charges. For more information on fields, refer to the field description table.

**Table 5-2 Charge Details - Field Description**

Field	Description
<b>Total Charges</b>	Displays the total charges in transaction currency (TCY) and branch local currency (LCY).
<b>Detailed View</b>	<p>Displays the following charge details of each charge code:</p> <ul style="list-style-type: none"> <li>• Charge Code</li> <li>• Currency</li> <li>• Charge Amount</li> <li>• Waiver</li> <li>• Charge By Cash</li> <li>• Charge TCY</li> <li>• Charge LCY</li> <li>• Basis</li> <li>• Min Charge</li> <li>• Max Charge</li> <li>• Price Rule Id</li> <li>• Credit Account</li> <li>• Debit Account</li> </ul>
<b>Charge Code</b>	The system defaults the charge components applicable to the transaction.
<b>Currency</b>	Displays the currency in which the charge has to be deducted.
<b>Charge Amount</b>	<p>Displays the charge amount that needs to be deducted for the corresponding charge component.</p> <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>The charge amount can be modified only if the field is enabled in the <b>Function Code Preferences</b> screen. The modified charge amount will be validated against the minimum and maximum charge amount that can be configured at the <b>Charge Maintenance</b> screen. When an individual charge amount is modified, the system will recalculate all the dependent charges.</p> </div>

**Table 5-2 (Cont.) Charge Details - Field Description**

Field	Description
<b>Waiver</b>	<p>If necessary, check this box against the charge component to waive a certain charge for the customer.</p> <div data-bbox="906 432 1458 808" style="border-left: 2px solid #0070C0; padding-left: 10px; margin-left: 20px;"> <p> <b>Note:</b></p> <p>When the <b>Waiver</b> is enabled, the value under <b>Charge Amount</b> will be waived and no charge accounting entries will be passed. The charge waiver can be enabled at individual charge level without impacting other linked charges. The minimum charge amount configured at the charge maintenance level, will not be validated when the charge is waived.</p> </div>
<b>Charge By Cash</b>	Indicates whether the charges are to be collected by cash.

## 5.2 Cash Withdrawal

The **Cash Withdrawal** screen is used to withdraw funds from the CASA account of the customer.

The withdrawal is subject to the availability of a sufficient balance or available credit limit. When the transaction is performed, it updates the available balance in the CASA account immediately.

To withdraw cash:

1. On the **Home** screen, from **Teller** mega menu, under **Customer Transaction**, click **Cash Withdrawal** or specify **Cash Withdrawal** in the search icon bar and select the screen.

The **Cash Withdrawal** screen is displayed.

Figure 5-3 Cash Withdrawal

2. On the **Cash Withdrawal** screen, specify the fields. For more information on fields, refer to the field description table.

Table 5-3 Cash Withdrawal - Field Description

Field	Description
<b>Account Number</b>	Specify a valid customer account number.  <div style="border: 1px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b> When you press the <b>Tab</b> key, the corresponding account information will be displayed in the <b>Customer Information</b> widget. The system displays an override or error message on the tab out of Account Number based on the account dormancy parameters.</p> </div>
<b>Transaction Amount</b>	Displays the local currency of the branch. You can also select another currency from the drop-down values. Specify the transaction amount that needs to be debited from the customer account.

**Table 5-3 (Cont.) Cash Withdrawal - Field Description**





Field	Description
<b>Exchange Rate</b>	<p>Displays the exchange rate used to convert the transaction currency into account currency, and it can be modified.</p> <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>If the transaction currency is the same as the account currency, the system displays the exchange rate as 1. This field is displayed only if <code>Multi-Currency Configuration</code> at Function Code Indicator level is set as Y.</p> </div>
<b>Negotiated Exchange Rate</b>	<p>Specify the negotiated exchange rate that should be used for foreign currency transactions between the treasury and the branch. You need to specify the negotiated exchange rate only when the currencies involved in the transaction are different.</p> <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>This field is applicable only if the transaction involves cross currency and only if <code>cross currency enabled</code> and <code>Negotiated_Rate_Enabled</code> Configuration at Function Code Indicator level is set as Y.</p> </div>
<b>Negotiated Reference Number</b>	<p>Specify the unique reference number that should be used for negotiation of cost rate, in foreign currency transaction. If you have specified the negotiated cost rate, then you need to specify the negotiated reference number also.</p>
<b>Account Amount</b>	<p>Displays the transaction amount converted in terms of account amount based on the exchange rate.</p> <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>This field is displayed only if <code>Multi-Currency Configuration</code> at Function Code Indicator level is set as Y.</p> </div>

Table 5-3 (Cont.) Cash Withdrawal - Field Description

Field	Description
<b>Total Charge Amount</b>	<p>Displays the total charge amount, which is computed by the system in the local currency of the branch.</p> <p> <b>Note:</b></p> <p>This field is displayed only if <code>Total Charges Configuration</code> at <code>Function Code Indicator</code> level is set as <code>Y</code>.</p>
<b>Narrative</b>	Displays the default narrative as <b>Cash Withdrawal</b> , and it can be modified.

- Specify the charge details. For information on the fields in the **Charge Details** segment, refer to [Charge Details](#).
- Specify the denomination details. For information on the fields in the **Denomination Details** segment, refer to [Add Denomination Details](#).
- Click **Submit**.

A teller sequence number is generated, and the `Transaction Completed Successfully` information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any approval warning raised when the transaction saves. On transaction completion, the cash is withdrawn successfully from the customer account. For more information on transaction submission and validations, refer to [Step 5 in Cash Deposit](#).

## 5.3 Check Withdrawal

The **Check Withdrawal** screen is used to withdraw cash from the CASA account of the customer against the in-house check.

The withdrawal is subject to the availability of a sufficient balance or available credit limit. To verify the signature for the transactions, you can click **Verify** button in the **Customer Information Widget**. The signature verification is applicable for the transactions, which have the `Signature Verification Required` option selected as `Y` at the `Function Code Preference` level.

To withdraw cash through the in-house check:

- On the **Home** screen, from **Teller** mega menu, under **Customer Transaction**, click **Check Withdrawal** or specify **Check Withdrawal** in the search icon bar and select the screen.

The **Check Withdrawal** screen is displayed.

Figure 5-4 Check Withdrawal

- On the **Check Withdrawal** screen, specify the fields. For more information on fields, refer to the field description table.

Table 5-4 Check Withdrawal - Field Description

Field	Description
<b>Account Number</b>	Specify a valid account number for the customer.  <div style="border: 1px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b></p> <p>When you press the <b>Tab</b> key, the corresponding account information will be displayed in the <b>Customer Information</b> widget. The system displays an override or error message on the tab out of Account Number based on the account dormancy parameters.</p> </div>
<b>Transaction Amount</b>	Displays the local currency of the branch. You can also select another currency from the drop-down list. Specify the transaction amount that needs to be debited from the customer account.
<b>Check Number</b>	Specify the check number of the customer account as provided by the Customer.  <div style="border: 1px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b></p> <p>The system validates the status of the check and prompts an error message if in case of a Used or Stopped or Invalid check.</p> </div>
<b>Check Date</b>	Select the date on which the check has been issued from the calendar option.

Table 5-4 (Cont.) Check Withdrawal - Field Description





Field	Description
<b>Exchange Rate</b>	<p>Displays the exchange rate used to convert the transaction currency into account currency and it can be modified.</p> <p> <b>Note:</b></p> <p>If the transaction currency is the same as the account currency, the system displays the exchange rate as 1. This field is displayed only if <code>Multi-Currency Configuration at Function Code Indicator</code> level is set as Y.</p>
<b>Negotiated Exchange Rate</b>	<p>Specify the negotiated exchange rate that should be used for foreign currency transactions between the treasury and the branch. You need to specify the negotiated exchange rate only when the currencies involved in the transaction are different.</p> <p> <b>Note:</b></p> <p>This field is applicable only if the transaction involves cross currency and only if <code>cross currency enabled</code> and <code>Negotiated_Rate_Enabled Configuration at Function Code Indicator</code> level is set as Y.</p>
<b>Negotiated Reference Number</b>	<p>Specify the unique reference number that should be used for negotiation of cost rate, in foreign currency transaction. If you have specified the negotiated cost rate, then you need to specify the negotiated reference number also.</p>
<b>Reject Code</b>	<p>Select the reject code from the list of values, which are maintained in the <b>Reject Code Maintenance</b> screen.</p> <p> <b>Note:</b></p> <ul style="list-style-type: none"> <li>• If the check withdrawal transaction needs to be rejected, you can reject it by specifying the appropriate reject code in this field. The transaction can be rejected for one of the following reasons: <ul style="list-style-type: none"> <li>– Insufficient funds</li> <li>– Signature mismatch</li> <li>– Stale check</li> </ul> </li> <li>• For the rejected check withdrawal transactions, the denomination details segment is disabled.</li> </ul>
<b>Reject Code Description</b>	<p>Displays the description of the specified reject code.</p>



Table 5-4 (Cont.) Check Withdrawal - Field Description

Field	Description
Account Amount	<p>Displays the transaction amount converted in terms of account amount based on the exchange rate.</p> <div style="border: 1px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b></p> <p>This field is displayed only if Multi-Currency Configuration at Function Code Indicator level is set as Y.</p> </div>
Narrative	Displays the default narrative as <b>Check Withdrawal</b> , and it can be modified.

3. Click **Submit**.

A teller sequence number is generated, and the `Transaction Completed Successfully` information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any approval warning raised when the transaction saves. On transaction completion, the cash is withdrawn successfully against the customer check. For more information on transaction submission and validations, refer to [Step 5 in Cash Deposit](#).

## 5.4 FX Sale Against Account

The Foreign Exchange (**FX**) **Sale Against Account** screen is used to sell the foreign currency from the branch through the CASA account.

This transaction is performed by debiting the corresponding account currency from the CASA account.

To sell the foreign currency against CASA account:

1. On the **Home** screen, from **Teller** mega menu, under **Customer Transaction** → **Forex Transactions**, click **FX Sale - Account** or specify **FX Sale - Account** in the search icon bar and select the screen.

The **FX Sale Against Account** screen is displayed.




Figure 5-5 FX Sale Against Account

2. On the **FX Sale Against Account** screen, specify the fields. For more information on fields, refer to the field description table.




Table 5-5 FX Sale Against Account - Field Description

Field	Description
<b>Account Number</b>	<p>Specify the CASA account to be debited for the foreign currency sale from the adjacent option list.</p> <div style="border: 1px solid #ccc; background-color: #e6f2ff; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>The system displays an override or error message on the tab out of Account Number based on the account dormancy parameters.</p> </div>
<b>Amount Sold</b>	<p>Specify the currency and amount sold against the CASA account. You can select the appropriate code from the adjoining option list that displays all the currency codes maintained in the system. The system also displays the amount that is being sold.</p>

**Table 5-5 (Cont.) FX Sale Against Account - Field Description**

Field	Description
<b>Allow Denom Variance</b>	<p>Select if the denomination-wise variance needs to be applied for the transaction.</p> <p> <b>Note:</b></p> <p>If the parameter at the function code indicator is set as Y, this option will be selected by default and it can be modified. If the parameter at the function code indicator is set as N, then this option will be disabled.</p>
<b>Beneficiary Name</b>	Displays the name of the beneficiary customer based on the account number selected.
<b>Address Line 1 to Address Line 4</b>	Displays the address of the beneficiary.
<b>Identification Type</b>	Select the type of identification provided by the customer from the drop-down list.
<b>Identification Number</b>	Specify the identification number provided by the customer.
<b>Exchange Rate</b>	<p>Displays the exchange rate used to convert the transaction (sale) currency into account currency and it can be modified.</p> <p> <b>Note:</b></p> <p>This field is displayed only if <code>Multi-Currency Configuration</code> at <code>Function Code Indicator</code> level is set as Y.</p>
<b>Negotiated Exchange Rate</b>	<p>Specify the negotiated exchange rate that should be used for foreign currency transactions between the treasury and the branch.</p> <p> <b>Note:</b></p> <p>This field is applicable only if the transaction involves cross currency and only if cross currency enabled and <code>Negotiated_Rate_Enabled</code> Configuration at <code>Function Code Indicator</code> level is set as Y.</p>

**Table 5-5 (Cont.) FX Sale Against Account - Field Description**

Field	Description
<b>Negotiated Reference Number</b>	<p>Specify the unique reference number that should be used for negotiation of cost rate, in foreign currency transaction. If you have specified the negotiated cost rate, then you need to specify the negotiated reference number also.</p> <p> <b>Note:</b></p> <p>Accounting system books the online revaluation entries based on the difference in exchange rate between the negotiated exchange rate and transaction rate.</p>
<b>Amount Received</b>	<p>Displays the amount received and currency from the CASA account.</p> <p> <b>Note:</b></p> <p>The currency of the amount received defaults from the CASA account currency. The amount received will be calculated based on the <b>Amount Sold</b> and the <b>Exchange Rate</b>. This field is displayed only if <b>Multi-Currency Configuration</b> at <b>Function Code Indicator</b> level is set as <b>Y</b>.</p>
<b>Total Charges</b>	<p>Displays the total charge amount which is computed by the system in the local currency of the branch.</p> <p> <b>Note:</b></p> <p>This field is displayed only if <b>Total Charges Configuration</b> at <b>Function Code Indicator</b> level is set as <b>Y</b>.</p>
<b>Narrative</b>	<p>Displays the default narrative as <b>FX Sale Against Account</b>, and it can be modified.</p>

3. Specify the charge details. For information on the fields in the **Charge Details** segment, refer to [Charge Details](#).
4. Specify the FX Out Denomination details. For information on the fields in the **Denomination Details** segment, refer to [Add Denomination Details](#).
5. Click **Submit**.

A teller sequence number is generated, and the **Transaction Completed Successfully** information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any approval warning raised when the transaction saves. On transaction completion, the foreign currency cash is withdrawn and the equivalent account amount is debited. For more information on transaction submission and validations, refer to *Step 5* in [Cash Deposit](#).

## 5.5 FX Sale Against Walk-in

The **FX Sale Against Walk-in** screen is used to sell a foreign currency to a walk-in customer in return for the equivalent amount received in any other currency.

To sell a foreign currency to the walk-in customer:

1. On the **Home** screen, from **Teller** mega menu, under **Customer Transaction** → **Forex Transactions**, click **FX Sale - Walk-in** or specify **FX Sale - Walk-in** in the search icon bar and select the screen.

The **FX Sale Against Walk-in** screen is displayed.

**Figure 5-6 FX Sale Against Walk-in**

2. On the **FX Sale Against Walk-in** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 5-6 FX Sale Against Walk-in - Field Description**

Field	Description
<b>Amount Sold</b>	Select the applicable currency from the drop-down list and specify the amount that needs to be sold to the walk-in customer.

Table 5-6 (Cont.) FX Sale Against Walk-in - Field Description







Field	Description
<b>Currency Received</b>	Select the currency that you have received from the customer in return for the currency sold. You can select the appropriate code from the adjoining option list that displays all the currency codes maintained in the system.
<b>Allow Denom Variance</b>	Select if the denomination-wise variance needs to be applied for the transaction.   <b>Note:</b>  If the parameter at function code indicator is set as Y, this option will be selected by default, and it can be modified. If the parameter at the function code indicator is set as N, then this option will be disabled.
<b>Beneficiary Name</b>	Specify the name of the beneficiary customer.
<b>Beneficiary Address 1 to Beneficiary Address 4</b>	Specify the address of the beneficiary.
<b>Identification Type</b>	Select the type of identification provided by the customer from the drop-down list.
<b>Identification Number</b>	Specify the identification number provided by the customer.
<b>Exchange Rate</b>	Displays the exchange rate used to convert the transaction currency into account currency, and it can be modified.   <b>Note:</b>  This field is displayed only if <code>Multi-Currency Configuration</code> at <code>Function Code Indicator</code> level is set as Y.
<b>Negotiated Exchange Rate</b>	Specify the negotiated exchange rate that should be used for foreign currency transactions between the treasury and the branch.   <b>Note:</b>  This field is applicable only if the transaction involves cross currency and only if <code>cross currency enabled</code> and <code>Negotiated_Rate_Enabled Configuration</code> at <code>Function Code Indicator</code> level is set as Y.

Table 5-6 (Cont.) FX Sale Against Walk-in - Field Description

Field	Description
<b>Negotiated Reference Number</b>	<p>Specify the unique reference number that should be used for negotiation of cost rate, in foreign currency transaction. If you have specified the negotiated cost rate, then you need to specify the negotiated reference number also.</p> <p> <b>Note:</b></p> <p>Accounting system books the online revaluation entries based on the difference in exchange rate between the negotiated exchange rate and transaction rate.</p>
<b>Amount Received</b>	<p>Displays the amount received and currency from the customer. The received amount includes charges.</p> <p> <b>Note:</b></p> <p>The currency of the amount received will be defaulted from <b>Currency Received</b>. The amount received will be calculated based on the <b>Amount Sold</b> and the <b>Exchange Rate</b>. This field is displayed only if <i>Multi-Currency Configuration</i> at Function Code Indicator level is set as Y.</p>
<b>Total Charges</b>	<p>Displays the total charge amount, which is computed by the system in the local currency of the branch.</p> <p> <b>Note:</b></p> <p>This field is displayed only if <i>Total Charges Configuration</i> at Function Code Indicator level is set as Y.</p>
<b>Narrative</b>	<p>Displays the default narrative as <b>FX Sale (Walk-in)</b>, and it can be modified.</p>

3. Specify the charge details. For information on the fields in the **Charge Details** segment, refer to [Charge Details](#).
4. Specify the FX In Denomination details. For information on the fields in the **FX In Denomination Details** segment, refer to [Add Denomination Details](#).
5. Specify the FX Out Denomination details. For information on the fields in the **FX Out Denomination Details** segment, refer to [Add Denomination Details](#).
6. Click **Submit**.

A teller sequence number is generated, and the Transaction Completed Successfully information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any approval warning raised when the transaction saves. On transaction completion, the teller cash position to the equivalent of "Sold currency" is deducted, and "Received currency" is incremented. For more information on transaction submission and validations, refer to *Step 5* in [Cash Deposit](#).

## 5.6 FX Purchase Against Account

The **FX Purchase Against Account** screen is used to purchase foreign currency from the branch through the CASA account.

This transaction is performed by crediting the corresponding amount to the CASA account.

To purchase foreign currency against the CASA account:

1. On the **Home** screen, from **Teller** mega menu, under **Customer Transaction** → **Forex Transactions**, click **FX Purchase - Account** or specify **FX Purchase - Account** in the search icon bar and select the screen.

The **FX Purchase Against Account** screen is displayed.

**Figure 5-7 FX Purchase Against Account**

The screenshot displays the 'Teller Transaction - Fx Purchase Against Account' interface. At the top, there is a title bar with the transaction ID 'TRN-0062308900034446' and the branch date 'Mar 30, 2018'. Below the title bar, the main form is organized into several sections:

- Account Information:** Includes fields for 'Account Number' (marked as Required), 'Amount Bought' (with a dropdown and 'Required' label), and 'Allow Denom Variance' (a toggle switch).
- Beneficiary Information:** Contains fields for 'Beneficiary Name', 'Beneficiary Address 1' through 'Beneficiary Address 4', 'Identification Type' (dropdown), and 'Identification Number'.
- Transaction Parameters:** Includes 'Exchange Rate' (with a value of '1'), 'Negotiated Reference Number', 'Negotiated Exchange Rate', 'Total Charges', and 'Narrative' (with a pre-filled text 'FX Purchase against Account').
- Summary/Action:** At the bottom, there are 'Charge Details' and 'Denomination' sections, and 'Cancel', 'Submit', and 'Clear' buttons.

On the right side, a sidebar provides additional context: 'Current Till Position' with a gauge showing 'E0.89M' and 'Filters' set to 'GBP' (with 'Min: 0' and 'Max: 9999,999'). Below this, 'Memo Alerts' shows 'No Data to Display', and 'Frequent Customer Operations' is listed at the bottom.

2. On the **FX Purchase Against Account** screen, specify the fields. For more information on fields, refer to the field description table.



**Table 5-7 FX Purchase Against Account - Field Description**








Field	Description
<b>Account Number</b>	<p>Specify the CASA account number to be credited for the foreign currency purchase.</p> <div style="border: 1px solid #0070C0; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>In addition, you can use Oracle Banking Virtual Accounts. These Virtual Accounts are used as a routing account to credit the underlying physical account.</p> <p>The system displays an override or error message on the tab out of Account Number based on the account dormancy parameters.</p> </div>
<b>Amount Bought</b>	Select the applicable currency from the drop-down list, and specify the amount that needs to be bought from the customer.
<b>Allow Denom Variance</b>	<p>Select if the denomination-wise variance needs to be applied for the transaction.</p> <div style="border: 1px solid #0070C0; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>If the parameter at the function code indicator is set as Y, this option will be selected by default, and it can be modified. If the parameter at function code indicator is set as N, then this option will be disabled.</p> </div>
<b>Beneficiary Name</b>	Displays the name of the beneficiary customer based on the account number provided.
<b>Beneficiary Address 1 to Beneficiary Address 4</b>	Displays the address of the beneficiary.
<b>Identification Type</b>	Select the type of identification provided by the customer from the drop-down list.
<b>Identification Number</b>	Specify the identification number provided by the customer.
<b>Exchange Rate</b>	<p>Displays the exchange rate used to convert the transaction currency into account currency, and it can be modified.</p> <div style="border: 1px solid #0070C0; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>This field is displayed only if <i>Multi-Currency Configuration at Function Code Indicator level</i> is set as Y.</p> </div>

Table 5-7 (Cont.) FX Purchase Against Account - Field Description

Field	Description
<b>Negotiated Exchange Rate</b>	<p>Specify the negotiated exchange rate that should be used for foreign currency transactions between the treasury and the branch. You need to specify the negotiated exchange rate only when the currencies involved in the transaction are different.</p> <p> <b>Note:</b></p> <p>This field is applicable only if the transaction involves cross currency and only if cross currency enabled and <code>Negotiated_Rate_Enabled</code> Configuration at Function Code Indicator level is set as Y.</p>
<b>Negotiated Reference Number</b>	<p>Specify the unique reference number that should be used for negotiation of cost rate, in foreign currency transaction. If you have specified the negotiated cost rate, then you need to specify the negotiated reference number also.</p> <p> <b>Note:</b></p> <p>Accounting system books the online revaluation entries based on the difference in exchange rate between the negotiated exchange rate and transaction rate.</p>
<b>Amount Paid</b>	<p>Displays the amount paid and currency to the CASA account.</p> <p> <b>Note:</b></p> <p>The currency of the amount paid is defaulted from the account currency. The <b>Amount Paid</b> will be calculated based on the <b>Amount Bought</b> and the <b>Exchange Rate</b>. This field is displayed only if <code>Multi-Currency Configuration</code> at Function Code Indicator level is set as Y.</p>
<b>Total Charges</b>	<p>Displays the total charge amount, which is computed by the system in the local currency of the branch.</p> <p> <b>Note:</b></p> <p>This field is displayed only if <code>Total Charges Configuration</code> at Function Code Indicator level is set as Y.</p>

**Table 5-7 (Cont.) FX Purchase Against Account - Field Description**

Field	Description
Narrative	Displays the default narrative as <b>FX Purchase Against Account</b> , and it can be modified.

3. Specify the charge details. For information on the fields in the **Charge Details** segment, refer to [Charge Details](#).
4. Specify the FX In Denomination details. For information on the fields in the **Denomination Details** segment, refer to [Add Denomination Details](#).
5. Click **Submit**.

A teller sequence number is generated, and the `Transaction Completed Successfully` information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any approval warning raised when the transaction saves. On transaction completion, the teller's cash position gets incremented based on the amount bought.

In addition, the corresponding foreign currency cash is deposited for an equivalent amount of credit in the customer's account. For more information on transaction submission and validations, refer to *Step 5* in [Cash Deposit](#).

## 5.7 FX Purchase Against Walk-in

The **FX Purchase Against Walk-in** screen is used to buy a foreign currency from a walk-in customer in return for the equivalent amount in any other currency.

To buy a foreign currency from a walk-in customer:

1. On the **Home** screen, from **Teller** mega menu, under **Customer Transaction** → **Forex Transactions**, click **FX Purchase - Walk-in** or specify **FX Purchase - Walk-in** in the search icon bar and select the screen.

The **FX Purchase Against Walk-in** screen is displayed.

Figure 5-8 FX Purchase Against Walk-in

- On the **FX Purchase Against Walk-in** screen, specify the fields. For more information on fields, refer to the field description table.

Table 5-8 FX Purchase Against Walk-in

Field	Description
<b>Amount Bought</b>	Select the applicable currency from the drop-down list, and specify the amount bought from the walk-in customer.
<b>Currency Paid</b>	Select the currency that you have paid to the walk-in customer.  <div style="border: 1px solid #ccc; background-color: #e6f2ff; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>You can select the appropriate code from the list of values that displays all the currency codes maintained in the system.</p> </div>

Table 5-8 (Cont.) FX Purchase Against Walk-in







Field	Description
<b>Allow Denom Variance</b>	<p>Select if the denomination-wise variance needs to be applied for the transaction.</p> <p> <b>Note:</b></p> <p>If the parameter at function code indicator is set as Y, this option will be selected by default, and it can be modified. If the parameter at the function code indicator is set as N, then this option will be disabled.</p>
<b>Beneficiary Name</b>	Specify the name of the beneficiary walk-in customer.
<b>Beneficiary Address 1 to Beneficiary Address 4</b>	Specify the address of the beneficiary walk-in customer.
<b>Identification Type</b>	Select the type of identification provided by the walk-in customer from the drop-down list.
<b>Identification Number</b>	Specify the identification number provided by the walk-in customer.
<b>Exchange Rate</b>	<p>Displays the exchange rate used to convert the transaction currency into account currency, and it can be modified.</p> <p> <b>Note:</b></p> <p>This field is displayed only if Multi-Currency Configuration at Function Code Indicator level is set as Y.</p>
<b>Negotiated Exchange Rate</b>	<p>Specify the negotiated exchange rate that should be used for foreign currency transactions between the treasury and the branch. You need to specify the negotiated exchange rate only when the currencies involved in the transaction are different.</p> <p> <b>Note:</b></p> <p>This field is applicable only if the transaction involves cross currency and only if cross currency enabled and Negotiated_Rate_Enabled Configuration at Function Code Indicator level is set as Y.</p>

Table 5-8 (Cont.) FX Purchase Against Walk-in

Field	Description
<b>Negotiated Reference Number</b>	<p>Specify the unique reference number that should be used for negotiation of cost rate, in foreign currency transaction. If you have specified the negotiated cost rate, then you need to specify the negotiated reference number also.</p> <p> <b>Note:</b></p> <p>Accounting system books the online revaluation entries based on the difference in exchange rate between the negotiated exchange rate and transaction rate.</p>
<b>Amount Paid</b>	<p>Displays the amount paid and currency to the customer.</p> <p> <b>Note:</b></p> <p>The currency of the amount paid is defaulted from the received currency. The <b>Amount Paid</b> will be calculated based on the <b>Amount Bought</b> and the <b>Exchange Rate</b>. This field is displayed only if <b>Multi-Currency Configuration</b> at Function Code Indicator level is set as Y.</p>
<b>Total Charges</b>	<p>Displays the total charge amount, which is computed by the system in the local currency of the branch.</p> <p> <b>Note:</b></p> <p>This field is displayed only if <b>Multi-Currency Configuration</b> at Function Code Indicator level is set as Y.</p>
<b>Narrative</b>	<p>Displays the default narrative as <b>FX Purchase (Walk-in)</b>, and it can be modified.</p>

3. Specify the charge details. For information on the fields in the **Charge Details** segment, refer to [Charge Details](#).
4. Specify the FX In Denomination details. For information on the fields in the **FX In Denomination Details** segment, refer to [Add Denomination Details](#).
5. Specify the FX Out Denomination details. For information on the fields in the **FX Out Denomination Details** segment, refer to [Add Denomination Details](#).
6. Click **Submit**.

A teller sequence number is generated, and the `Transaction Completed Successfully` information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any approval warning raised when the transaction saves. On transaction completion, the teller cash position is updated based on the currency of the **Amount Bought** and the **Amount Paid** fields. For more information on transaction submission and validations, refer to *Step 5* in [Cash Deposit](#).

# 6

## Miscellaneous Transactions

The Teller can use Miscellaneous Transactions to perform GL transactions against a customer's CASA account and GL account.

This topic contains the following subtopics:

- [Miscellaneous Customer Debit](#)  
The **Miscellaneous Customer Debit** screen is used to transfer funds from the customer account to GL.
- [Miscellaneous Customer Credit](#)  
The **Miscellaneous Customer Credit** screen is used to transfer funds from GL to the customer account.
- [Miscellaneous GL Debit](#)  
The **Miscellaneous GL Debit** screen is used to debit an amount from a GL account of the transaction branch and pay out the equivalent amount in cash.
- [Miscellaneous GL Credit](#)  
The **Miscellaneous GL Credit** screen is used to credit an amount to a GL account of the transaction branch by pay-in of equivalent amount in cash.
- [Miscellaneous GL Transfer](#)  
The **Miscellaneous GL Transfer** screen is used to transfer the amount from a GL account to another GL account.
- [Miscellaneous Transfer](#)  
The **Miscellaneous Transfer** screen is used to facilitate transfer between the two different GLs or customer accounts.

### 6.1 Miscellaneous Customer Debit

The **Miscellaneous Customer Debit** screen is used to transfer funds from the customer account to GL.

The customer account can be debited for various reasons, with a corresponding credit to a GL belonging to the transaction branch.

To transfer funds from the customer account to GL:

1. On the **Home** screen, from **Teller** mega menu, under **Miscellaneous**, click **Misc Customer Debit** or specify **Misc Customer Debit** in the search icon bar and select the screen.

The **Miscellaneous Customer Debit** screen is displayed.






**Figure 6-1 Miscellaneous Customer Debit**

2. On the **Miscellaneous Customer Debit** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 6-1 Miscellaneous Customer Debit - Field Description**

Field	Description
<b>Account Number</b>	Specify the account number from which the funds need to be debited.  <b>Note:</b> The system displays an override or error message on the tab out of Account Number based on the account dormancy parameters.
<b>Account Amount</b>	Displays the account currency based on the account number specified. Specify the amount that needs to be debited from the account currency.
<b>GL Account</b>	Specify the GL account to which the funds need to be credited.  <b>Note:</b> You can also select the appropriate GL account from the list of values that displays all the valid GL accounts.
<b>GL Branch</b>	Displays the branch code of the transaction branch, and it can be modified.
<b>GL Description</b>	Displays the description of the selected GL account number.
<b>GL Currency</b>	By default, the account currency is displayed, and it can be modified.

Table 6-1 (Cont.) Miscellaneous Customer Debit - Field Description

Field	Description
<b>Exchange Rate</b>	<p>Displays the exchange rate used to convert the transaction currency into GL currency, and it can be modified.</p> <p> <b>Note:</b></p> <p>If the transaction currency is the same as the account currency, the system displays the exchange rate as 1. This field is displayed only if <code>Multi-Currency Configuration</code> at Function Code Indicator level is set as Y.</p>
<b>Negotiated Exchange Rate</b>	<p>Specify the negotiated exchange rate that should be used for foreign currency transactions between the treasury and the branch. You need to specify the negotiated exchange rate only when the currencies involved in the transaction are different.</p> <p> <b>Note:</b></p> <p>This field is applicable only if the transaction involves cross currency and only if <code>cross currency enabled</code> and <code>Negotiated_Rate_Enabled Configuration</code> at Function Code Indicator level is set as Y.</p>
<b>Negotiated Reference Number</b>	<p>Specify the unique reference number that should be used for negotiation of cost rate, in foreign currency transaction. If you have specified the negotiated cost rate, then you need to specify the negotiated reference number also.</p>
<b>GL Amount</b>	<p>Displays the amount in terms of GL currency.</p> <p> <b>Note:</b></p> <p>This field is displayed only if <code>Multi-Currency Configuration</code> at Function Code Indicator level is set as Y.</p>
<b>Reference Number</b>	<p>Specify the reference number for the transaction, which is the original transaction reference or any invoice number.</p>
<b>Narrative</b>	<p>Displays the narrative as <b>Miscellaneous Customer Debit</b>, and it can be modified.</p>

- Specify the charge details. For information on the fields in the **Charge Details** segment, refer to [Charge Details](#).
- Click **Submit**.

A teller sequence number is generated, and the Transaction Completed Successfully information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any approval warning raised when the transaction saves.

## 6.2 Miscellaneous Customer Credit

The **Miscellaneous Customer Credit** screen is used to transfer funds from GL to the customer account.


The customer account can be credited for various reasons, with the corresponding debit to a GL belonging to the transaction branch.

To perform the miscellaneous customer credit:

1. On the **Home** screen, from **Teller** mega menu, under **Miscellaneous**, click **Misc Customer Credit** or specify **Misc Customer Credit** in the search icon bar and select the screen.




The **Miscellaneous Customer Credit** screen is displayed.

**Figure 6-2 Miscellaneous Customer Credit**





2. On the **Miscellaneous Customer Credit** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 6-2 Miscellaneous Customer Credit - Field Description**

Field	Description
<b>Account Number</b>	<p>Specify the account number from which the funds need to be credited.</p> <div style="border: 1px solid #0070C0; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>The system displays an override or error message on the tab out of Account Number based on the account dormancy parameters.</p> </div>
<b>Account Amount</b>	Displays the account currency based on the account number specified. Specify the amount to be credited from the account currency.
<b>GL Account</b>	<p>Specify the GL account from which the funds need to be debited.</p> <div style="border: 1px solid #0070C0; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>You can also select the appropriate GL account from the list of values that displays all the valid GL accounts.</p> </div>
<b>GL Branch</b>	Displays the branch code of the transaction branch and allows to modify.
<b>GL Description</b>	Displays the description of the selected GL account number.
<b>GL Currency</b>	By default, the account currency is displayed, and it can be modified.
<b>Exchange Rate</b>	<p>Displays the exchange rate used to convert the transaction currency into GL currency, and it can be modified.</p> <div style="border: 1px solid #0070C0; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>If the transaction currency is the same as the account currency, the system displays the exchange rate as 1. This field is displayed only if <b>Multi-Currency Configuration</b> at <b>Function Code Indicator</b> level is set as <b>Y</b>.</p> </div>

**Table 6-2 (Cont.) Miscellaneous Customer Credit - Field Description**

Field	Description
<b>Negotiated Exchange Rate</b>	<p>Specify the negotiated exchange rate that should be used for foreign currency transactions between the treasury and the branch. You need to specify the negotiated exchange rate only when the currencies involved in the transaction are different.</p> <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>This field is applicable only if the transaction involves cross currency and only if cross currency enabled and <code>Negotiated_Rate_Enabled</code> Configuration at Function Code Indicator level is set as Y.</p> </div>
<b>Negotiated Reference Number</b>	<p>Specify the unique reference number that should be used for negotiation of cost rate, in foreign currency transaction. If you have specified the negotiated cost rate, then you need to specify the negotiated reference number also.</p>
<b>GL Amount</b>	<p>Displays the amount in terms of GL currency.</p> <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>This field is displayed only if <code>Multi-Currency Configuration</code> at Function Code Indicator level is set as Y.</p> </div>
<b>Reference Number</b>	<p>Specify the reference number for the transaction, which is the original transaction reference or any invoice number.</p>
<b>Narrative</b>	<p>Displays the narrative as <b>Miscellaneous Customer Credit</b>, and it can be modified.</p>

3. Specify the charge details. For information on the fields in the **Charge Details** segment, refer to [Charge Details](#).
4. Click **Submit**.

A teller sequence number is generated, and the `Transaction Completed Successfully` information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any approval warning raised when the transaction saves. On transaction completion, the GL account is debited, and the customer account is credited to the extent of the **Account Amount**.

## 6.3 Miscellaneous GL Debit

The **Miscellaneous GL Debit** screen is used to debit an amount from a GL account of the transaction branch and pay out the equivalent amount in cash.

To perform miscellaneous GL debit:


1. On the **Home** screen, from **Teller** mega menu, under **Miscellaneous**, click **Misc GL Debit** or specify **Misc GL Debit** in the search icon bar and select the screen.

The **Miscellaneous GL Debit** screen is displayed.

**Figure 6-3 Miscellaneous GL Debit**

2. On the **Miscellaneous GL Debit** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 6-3 Miscellaneous GL Debit - Field Description**

Field	Description
<b>GL Account</b>	Specify the GL account from which the funds need to be debited.  <div style="border-left: 2px solid #0070C0; padding-left: 10px; background-color: #E6F2FF;"> <p> <b>Note:</b> You can also select the appropriate GL account from the list of values that displays all the valid GL accounts.</p> </div>
<b>GL Description</b>	Displays the description of the selected GL account number.

**Table 6-3 (Cont.) Miscellaneous GL Debit - Field Description**





Field	Description
<b>Transaction Amount</b>	<p>Specify the appropriate currency and the amount that has to be credited to the cash account in the specified currency.</p> <div data-bbox="740 394 1451 567" style="background-color: #e6f2ff; padding: 10px;"> <p> <b>Note:</b></p> <p>By default, the local currency of the branch is displayed. You can select another currency if required.</p> </div>
<b>GL Currency</b>	<p>Displays the branch account currency and allows to modify if required.</p>
<b>GL Amount</b>	<p>Displays the amount which is credited to the GL account.</p> <div data-bbox="740 747 1451 957" style="background-color: #e6f2ff; padding: 10px;"> <p> <b>Note:</b></p> <p>This field is displayed only if Multi-Currency Configuration at the Function Code Indicator level is set as Y.</p> </div>
<b>Exchange Rate</b>	<p>Displays the exchange rate used to convert the transaction currency into GL currency, and it can be modified.</p> <div data-bbox="740 1096 1451 1360" style="background-color: #e6f2ff; padding: 10px;"> <p> <b>Note:</b></p> <p>If the transaction currency is the same as the account currency, the system displays the exchange rate as 1. This field is displayed only if Multi-Currency Configuration at the Function Code Indicator level is set as Y.</p> </div>
<b>Negotiated Exchange Rate</b>	<p>Specify the negotiated exchange rate that should be used for foreign currency transactions between the treasury and the branch. You need to specify the negotiated exchange rate only when the currencies involved in the transaction are different.</p> <div data-bbox="740 1558 1451 1793" style="background-color: #e6f2ff; padding: 10px;"> <p> <b>Note:</b></p> <p>This field is applicable only if the transaction involves cross currency and only if cross currency enabled and Negotiated_Rate_Enabled Configuration at Function Code Indicator level is set as Y.</p> </div>

Table 6-3 (Cont.) Miscellaneous GL Debit - Field Description

Field	Description
<b>Negotiated Reference Number</b>	Specify the unique reference number that should be used for negotiation of cost rate, in foreign currency transaction. If you have specified the negotiated cost rate, then you need to specify the negotiated reference number also.
<b>Reference Number</b>	Specify the reference number for the transaction.
<b>Narrative</b>	Displays the default narrative as <b>Miscellaneous GL Debit</b> , and it can be modified.

- Specify the charge details. For information on the fields in the **Charge Details** segment, refer to [Charge Details](#).
- Specify the denomination details. For information on the fields in the **Denomination Details** segment, refer to [Add Denomination Details](#).
- Click **Submit**.

A teller sequence number is generated, and the `Transaction Completed Successfully` information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any warning raised when the transaction saves. On transaction completion, the cash balance of the Teller is updated successfully.

## 6.4 Miscellaneous GL Credit

The **Miscellaneous GL Credit** screen is used to credit an amount to a GL account of the transaction branch by pay-in of equivalent amount in cash.

To perform miscellaneous GL credit:

- On the **Home** screen, from **Teller** mega menu, under **Miscellaneous**, click **Misc GL Credit** or specify **Misc GL Credit** in the search icon bar and select the screen.

The **Miscellaneous GL Credit** screen is displayed.






**Figure 6-4 Miscellaneous GL Credit**

2. On the **Miscellaneous GL Credit** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 6-4 Miscellaneous GL Credit - Field Description**

Field	Description
<b>GL Account</b>	Specify the GL account to which the funds need to be credited.  <div style="border: 1px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b> You can also select the appropriate GL account from the list of values that displays all the valid GL accounts.</p> </div>
<b>GL Amount</b>	Displays the branch account currency and allows to modify if required. It also displays the amount which is credited to the GL account.  <div style="border: 1px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b> This field is displayed only if <b>Multi-Currency Configuration</b> at the <b>Function Code Indicator</b> level is set as <b>Y</b>.</p> </div>
<b>GL Description</b>	Displays the description of the selected GL account number.

Table 6-4 (Cont.) Miscellaneous GL Credit - Field Description

Field	Description
<b>Transaction Amount</b>	Specify the appropriate currency and the amount that has to be debited from the cash account in the specified currency.   <b>Note:</b>  By default, the local currency of the branch is displayed. You can select another currency if required.
<b>Negotiated Exchange Rate</b>	Specify the negotiated exchange rate if it is needed to perform the transaction using negotiated value.   <b>Note:</b>  This field is applicable only if the transaction involves cross currency. If this option is selected, the <b>Negotiated Reference Number</b> field will become mandatory.
<b>Negotiated Reference Number</b>	Specify the reference number for the negotiated cost rate.
<b>Narrative</b>	Displays the default narrative as <b>Miscellaneous GL Credit</b> , and it can be modified.
<b>Reference Number</b>	Specify the reference number for the transaction.
<b>Exchange Rate</b>	Displays the exchange rate used to convert the transaction currency into GL currency, and it can be modified.   <b>Note:</b>  If the transaction currency is the same as the account currency, the system displays the exchange rate as 1. This field is displayed only if <b>Multi-Currency Configuration at the Function Code Indicator</b> level is set as Y.

- Specify the charge details. For information on the fields in the **Charge Details** segment, refer to [Charge Details](#).
- Specify the denomination details. For information on the fields in the **Denomination Details** segment, refer to [Add Denomination Details](#).
- Click **Submit**.

A teller sequence number is generated, and the *Transaction Completed Successfully* information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any warning raised when the transaction saves. On transaction completion, the cash balance of the Teller gets updated successfully.

## 6.5 Miscellaneous GL Transfer

The **Miscellaneous GL Transfer** screen is used to transfer the amount from a GL account to another GL account.

This transaction can be carried out in various allowed currencies.

To perform miscellaneous GL transfer:




1. On the **Home** screen, from **Teller** mega menu, under **Miscellaneous**, click **Misc GL Transfer** or specify **Misc GL Transfer** in the search icon bar and select the screen.

The **Miscellaneous GL Transfer** screen is displayed.

**Figure 6-5 Miscellaneous GL Transfer**

2. On the **Miscellaneous GL Transfer** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 6-5 Miscellaneous GL Transfer - Field Description**

Field	Description
<b>From GL Account</b>	<p>Specify the GL account to which the funds need to be debited.</p> <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>You can also select the appropriate GL account from the list of values that displays all the valid GL accounts.</p> </div>
<b>From GL Amount</b>	Displays the branch account currency and allows to modify if required. It also displays the amount, which is debited from the GL account.
<b>From GL Description</b>	Displays the description of the selected GL account number.
<b>GL Currency</b>	Displays the branch currency and allows to modify if required.
<b>From GL Branch</b>	Click the search icon, and select the <b>From GL Branch</b> from the list of values.
<b>To GL Account</b>	<p>Specify the GL account to which the funds need to be credited.</p> <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>You can also select the appropriate GL account from the list of values that displays all the valid GL accounts.</p> </div>
<b>To GL Amount</b>	Displays the branch account currency and allows to modify if required. It also displays the amount, which is credited to the GL account.
<b>To GL Description</b>	Displays the description of the selected GL account number.
<b>GL Currency</b>	Displays the branch currency and allows to modify if required.
<b>To GL Branch</b>	Click the search icon, and select the <b>To GL Branch</b> from the list of values.
<b>Narrative</b>	Displays the default narrative as <b>Miscellaneous GL Transfer</b> , and it can be modified.
<b>Reference Number</b>	Specify the reference number for the transaction.
<b>Exchange Rate</b>	<p>Displays the exchange rate used to convert the transaction currency into GL currency, and it can be modified.</p> <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>If the transaction currency is the same as the account currency, the system displays the exchange rate as 1. This field is displayed only if Multi-Currency Configuration at Function Code Indicator level is set as Y.</p> </div>

3. Specify the charge details. For information on the fields in the **Charge Details** segment, refer to [Charge Details](#).
4. Click **Submit**.

A teller sequence number is generated, and the `Transaction Completed Successfully` information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any warning raised when the transaction saves.

## 6.6 Miscellaneous Transfer

The **Miscellaneous Transfer** screen is used to facilitate transfer between the two different GLs or customer accounts.

This transaction can be carried out between:

- GL to GL
- GL to Customer Account
- Customer Account to GL

To facilitate transfer using this screen, maintain as per the sample given below:

- Maintain static tags for the function code ACCL in the `SRV_TB_TX_STATIC_TAGS` table.
- Maintain actions URLs for function code ACCL in the `SRV_TB_BC_ACTIONS_URL` table.
- For the **Function Code Definition** screen,
  - Enable **Support Child Function Code** field for the function code 1000.
  - Maintain the **Parent Function Code** as 1000 for the function code ACCL.
- Maintain the function code preferences for ACCL.
- Maintain settlement definition for the ACCL function code with the Transaction Account/ GL and Offset Account/ GL.

To perform miscellaneous transfer:

1. On the **Home** screen, from **Teller** mega menu, under **Miscellaneous**, click **Miscellaneous Transfer** or specify **Miscellaneous Transfer** in the search icon bar and select the screen.

The **Miscellaneous Transfer** screen is displayed.

Figure 6-6 Miscellaneous Transfer

2. On the **Miscellaneous Transfer** screen, specify the fields. For more information on fields, refer to the field description table.

Table 6-6 Miscellaneous Transfer



Field	Description
<b>Function Code</b>	Click the search icon, and select the function code from the list of values, which contains only non-cash transactions.
<b>Currency</b>	Click the search icon, and select the currency from the list of values.   <b>Note:</b> By default, the currency field will default to the local branch currency, and it can be modified.
<b>Query</b>	Click <b>Query</b> to fetch the details.   <b>Note:</b> Based on the specified values of <b>Function Code</b> and <b>Currency</b> , the system populates <b>Debit Account</b> and <b>Credit Account</b> details. You can also modify the values.
<b>Debit Account Details</b>	Specify the fields under this section.

Table 6-6 (Cont.) Miscellaneous Transfer




Field	Description
<b>Debit Account</b>	Click the search icon, and select the debit account number from the list of values.
<b>Debit Account Name</b>	Displays the name of the specified debit account.
<b>Debit Account Branch</b>	Click the search icon, and select the debit account branch from the list of values.
<b>Debit Currency</b>	Click the search icon, and select the debit currency from the list of values.
<b>Debit Amount</b>	Specify the amount that needs to be debited.
<b>Credit Account Details</b>	Specify the fields under this section.
<b>Credit Account</b>	Click the search icon, and select the credit account number from the list of values.
<b>Credit Account Name</b>	Displays the name of the specified credit account.
<b>Credit Account Branch</b>	Click the search icon, and select the credit account branch from the list of values.
<b>Credit Currency</b>	Click the search icon, and select the credit currency from the list of values.
<b>Credit Amount</b>	Displays the credit amount based on the exchange rate pickup.  <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b> This field is displayed only if <code>Multi-Currency Configuration</code> at the <code>Function Code Indicator</code> level is set as <code>Y</code>.</p> </div>
<b>Exchange Rate</b>	Displays the exchange rate used to convert the transfer currency into transaction currency and it can be modified.  <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b> If the transfer currency is the same as the account currency, the system displays the exchange rate as 1. This field is displayed only if <code>Multi-Currency Configuration</code> at the <code>Function Code Indicator</code> level is set as <code>Y</code>.</p> </div>

Table 6-6 (Cont.) Miscellaneous Transfer

Field	Description
<b>Total Charges</b>	Displays the total charge amount, which is computed by the system.   <b>Note:</b>  This field is displayed only if Multi-Currency Configuration at the Function Code Indicator level is set as Y.
<b>Additional Details</b>	Specify the fields under this section.
<b>Reference Number</b>	Specify the reference number of the transaction.
<b>Narrative</b>	Displays the default narrative as <b>Miscellaneous Transfer</b> , and it can be modified.

3. Specify the charge details. For information on the fields in the **Charge Details** segment, refer to [Charge Details](#).
4. Click **Submit**.

A teller sequence number is generated, and the `Transaction Completed Successfully` information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any warning raised when the transaction saves.



# 7

## Branch Maintenance

The branch maintenance screens are used to perform the maintenance for processing the branch transactions.

This topic contains the following subtopics:

- [Maintain Denominations](#)  
The **Denominations Maintenance** screen is used to maintain the standard currency denominations for each currency that the bank deals with.
- [Maintain Inter Branch Transit Account](#)  
The **Inter Branch Transit Account** screen is used to maintain inter-branch transit account for each branch using the receiving branch, vault, and currency combination.
- [Maintain Teller Branch Parameters](#)  
The **Teller Branch Parameters Maintenance** screen is used to set the teller preferences for a branch.
- [Maintain Branch User Preferences](#)  
The **Branch User Limits** screen is used to set preferences like Till/Vault Indicator, currency holding preferences, and currency limit preferences for the branch user.
- [Maintain Channel Limits](#)  
The **Channel Limits** screen is used to maintain the channel limits for a particular customer group.
- [Maintain Function Code Definitions](#)  
The **Function Code Definition** screen is used to specify the preferences for the function code.
- [Maintain Branch Role Limits](#)  
The **Branch Role Limits** screen is used to set the input and authorization limits for a specific role.
- [Create Charge Pricing Maintenance](#)  
The **Create Charge Pricing Maintenance** screen is used to maintain the charge pricing.
- [View Charge Pricing Maintenance](#)  
The **View Charge Pricing Maintenance** screen is used to view the summary and details of charge pricing IDs.
- [Maintain Charge Definitions](#)  
The **Charge Definition Maintenance** screen is used to maintain the charge definitions.
- [Maintain Denomination Variance](#)  
The **Denomination Variance Maintenance** screen is used to maintain the denomination-wise variations.
- [Maintain Function Code Preferences](#)  
The **Function Code Preferences** screen is used to define the workflow preferences (validation preferences and authorization preferences) for a function code.

- [Maintain Accounting and Settlements](#)  
The **Settlements Definition** screen is used to define the settlement and accounting parameters that are applicable for processing the branch transactions involving a function code.
- [Maintain Reject Codes](#)  
The **Reject Code Maintenance** screen is used to maintain the reject codes.
- [Maintain Account Group](#)  
The **Account Group Maintenance** screen is used to create groups of the account codes, and these groups can be used for charge calculation.
- [Maintain External System](#)  
The **External System Maintenance** screen is used to define the parameters for the external system.
- [Maintain External Bank Codes](#)  
The **External Bank Code** screen is used to maintain the bank codes and branch codes.
- [Maintain Charge Decisions](#)  
The **Charge Decision Maintenance** screen is used to maintain the charge decisions.
- [Maintain Charge Condition Group](#)  
The **Charge Condition Group Maintenance** screen is used to create groups of the charge condition codes.
- [Maintain Customer Group](#)  
The **Customer Group Maintenance** screen is used to create groups of the customer codes, and these groups can be used for charge calculation.
- [Maintain Default Authorizer](#)  
The **Default Authorizer** screen is used to define the default authorizer who can authorize a specific function code for a branch user.
- [Maintain Branch Group](#)  
The **Branch Group Maintenance** screen is used to create groups of the branch codes, and these groups can be used for charge calculation.
- [Static Data](#)  
The **Static Data** screen is to populate the data for the static widgets.

## 7.1 Maintain Denominations

The **Denominations Maintenance** screen is used to maintain the standard currency denominations for each currency that the bank deals with.

For example, the denominations for the currency USD can be maintained as follows:

**Table 7-1 Denominations Maintenance for USD Currency**

CCY CODE	DENM CODE	DESCRIPTION	VALUE	NOTE / COIN
USD	D100	100 dollars	100	NOTE
USD	D50	50 dollars	50	NOTE
USD	D20	20 dollars	20	NOTE
USD	D10	10 dollars	10	NOTE

**Table 7-1 (Cont.) Denominations Maintenance for USD Currency**


CCY CODE	DENM CODE	DESCRIPTION	VALUE	NOTE / COIN
USD	D5	5 dollars	5	NOTE
USD	D1N	1 dollar	1	NOTE
USD	D1C	1 dollar	1	COIN
USD	C25	25 cents	0.25	COIN
USD	C10	10 cents	0.1	COIN
USD	C5	5 cents	0.05	COIN
USD	C1	1 cent	0.01	COIN

To maintain denominations:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Denominations Maintenance** or specify **Denominations Maintenance** in the search icon bar and select the screen.

The **Denominations Maintenance** summary screen is displayed.

**Figure 7-1 Denominations Maintenance (Summary)**



2. Click **Add** icon.

The **Denomination Maintenance (New)** screen is displayed.

**Figure 7-2 Denomination Maintenance**

3. On the **Denomination Maintenance** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-2 Denomination Maintenance - Field Description**

Field	Description
<b>Currency Code</b>	Specify the currency for which the currency denomination is to be maintained.
<b>Currency Description</b>	Specify the description of the currency code.
<b>Denomination Type</b>	Select the denomination type.
<b>Denomination Details</b>	Specify the fields.
<b>Denomination ID</b>	Specify the denomination code.
<b>Description</b>	Specify the description of the denomination code.
<b>Value</b>	Specify the numeric value of the denomination code.
<b>Sequence Number</b>	Specify the number such that the denomination codes will be displayed in the same sequence maintained.
<b>Type</b>	Specify the type as <b>Coin</b> or <b>Note</b> .
<b>Large Denomination</b>	Select if a particular denomination is to be maintained as a large denomination.
<b>Action</b>	Click the necessary icon to edit, save, or delete a row.

4. Click **Save**.  
The summary view is displayed with the configured denominations.

## 7.2 Maintain Inter Branch Transit Account


The **Inter Branch Transit Account** screen is used to maintain inter-branch transit account for each branch using the receiving branch, vault, and currency combination.

To maintain inter-branch transit account:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Inter Branch Transit Account** or specify **Inter Branch Transit Account** in the search icon bar and select the screen.

The **Inter Branch Transit Account** summary screen is displayed.


**Figure 7-3 Inter Branch Transit Account (Summary)**



2. Click **Add** icon.

The **Inter Branch Transit Account Maintenance** screen is displayed.

**Figure 7-4 Inter Branch Transit Account Maintenance**



3. On the **Inter Branch Transit Account Maintenance** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-3 Inter Branch Transit Account Maintenance - Field Description**

Field	Description
<b>Branch Code</b>	Select the branch code from the list of values, which provides all the branch codes maintained in the system.
<b>Branch Name</b>	Display the description of the selected branch code.
<b>Receiving Branch</b>	Specify the destination branch to which the cash is transferred.
<b>Branch Name</b>	Display the description of the selected Receiving Branch code.
<b>Currency</b>	Specify the currency of the cash.
<b>Transit Account</b>	Specify the transit account that is used to track the movement of cash.

**Table 7-3 (Cont.) Inter Branch Transit Account Maintenance - Field Description**

Field	Description
Action	Click the necessary icon to edit, save, or delete a row.

4. Click **Save**.

The summary view is displayed with the configured inter-branch transit account.

## 7.3 Maintain Teller Branch Parameters


The **Teller Branch Parameters Maintenance** screen is used to set the teller preferences for a branch.

To maintain teller branch parameters:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Teller Branch Parameters Maintenance** or specify **Teller Branch Parameters Maintenance** in the search icon bar and select the screen.

The **Teller Branch Parameters Maintenance** summary screen is displayed.


**Figure 7-5 Teller Branch Parameters Maintenance (Summary)**



2. Click **Add** icon.


The **Teller Branch Parameters Maintenance (New)** screen is displayed.

**Figure 7-6 Teller Branch Parameters Maintenance (New)**



- On the **Teller Branch Parameters Maintenance** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-4 Teller Branch Parameter Maintenance - Field Description**

Field	Description
<b>Branch Code</b>	Select the branch code from the list of the available options.
<b>Description</b>	Displays the description of the branch.
<b>Denomination Tracking Required</b>	Specify the denomination that needs to be tracked for the <b>Vault, Till and Vault</b> , or <b>None</b> . The descriptions of the drop-down values are given below: <ul style="list-style-type: none"> <li><b>Till and Vault</b> - To track denomination for Tills and Vault. By default, this option is selected.</li> <li><b>Vault</b> - To track denomination only for Vault, if a Vault is involved in the transaction.</li> <li><b>None</b> - To indicate that denomination tracking is not required for any transaction.</li> </ul>
<b>Currency Code</b>	Specify the currency for which the <b>Minimum Cash Holding Limit</b> or <b>Maximum Cash Holding Limit</b> is to be maintained for the branch.
<b>Minimum Cash Holding Limit</b>	Specify the minimum cash holding limit for the branch.
<b>Maximum Cash Holding Limit</b>	Specify the maximum cash holding limit for the branch. <div style="border: 1px solid #0070C0; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>The maximum cash holding amount must not be less than the minimum cash holding amount.</p> </div>
<b>Action</b>	Click the necessary icon to edit, save, or delete a row.

- Click **Save**.

The summary view is displayed with the configured teller branch parameters.

## 7.4 Maintain Branch User Preferences


The **Branch User Limits** screen is used to set preferences like Till/Vault Indicator, currency holding preferences, and currency limit preferences for the branch user.

To maintain branch user preferences:

- On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Branch User Limits** or specify **Branch User Limits** in the search icon bar and select the screen.


The **Branch User Limits** summary screen is displayed.

**Figure 7-7 Branch User Limits (Summary)**



2. Click **Add** icon.  
The **User Preferences** screen is displayed.

**Figure 7-8 User Preferences**




3. On the **User Preferences** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-5 User Preferences - Field Description**

Field	Description
<b>Branch Code</b>	Click the search icon, and select the branch code from the list of values.
<b>User ID</b>	Click the search icon, and select the user ID for which the branch preferences are to be maintained.



Table 7-5 (Cont.) User Preferences - Field Description

Field	Description
<b>Till/Vault Indicator</b>	Select from the following drop-down values: <ul style="list-style-type: none"> <li>• <b>Till</b></li> <li>• <b>Vault</b></li> <li>• <b>Both</b></li> <li>• <b>None</b></li> </ul>
<b>Shortage/Overage GL</b>	 <b>Note:</b> Currently not used, meant for future use.
<b>Carry Forward Allowed</b>	Select if the funds are allowed to carry forward for the next day.
<b>Inter Branch Transactions Allowed</b>	Select if the transfer between the branches is allowed.
<b>Receive Email</b>	Select if the Teller needs to receive emails for approval of transactions.
<b>Receive Notification</b>	Select if the Teller needs to receive notifications in Dashboard.
<b>Currency Holding Preferences</b>	Specify the fields.
<b>Currency Code</b>	Click the search icon, and select the currency code to specify the cash holding preferences.
<b>Minimum Balance</b>	Specify the minimum balance to be maintained for the Till or Vault.
<b>Maximum Balance</b>	Specify the maximum balance to be maintained for the Till or Vault.
<b>Currency Limit Preferences</b>	Specify the fields.
<b>Currency Code</b>	Click the search icon, and select the currency in which the limits (transactions amounts) will be expressed.
<b>Max Transaction Amount</b>	Specify the maximum transaction amount allowed that the user can enter in a single transaction.
<b>Authorization Limit</b>	Specify the maximum amount that the user (to which the limit role is associated) is allowed to process while authorizing a transaction.

4. Click **Save**.

The summary view is displayed with the configured user preferences.

## 7.5 Maintain Channel Limits


The **Channel Limits** screen is used to maintain the channel limits for a particular customer group.

To maintain channel limits:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Channel Limits** or specify **Channel Limits** in the search icon bar and select the screen.

The **Channel Limits** summary screen is displayed.


**Figure 7-9 Channel Limits (Summary)**



2. Click **Add** icon.



The **Channel Limits Maintenance** screen is displayed.

**Figure 7-10 Channel Limits Maintenance**



3. On the **Channel Limits Maintenance** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-6 Function Code Definition - Field Description**

Field	Description
<b>Account Group</b>	<p>Click the search icon and select account group from the list of values.</p> <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b></p> <p>The list of values provides the account groups that are maintained in the <b>Account Group Maintenance</b> screen.</p> </div>
<b>Channel</b>	<p>Select value from the drop-down list.</p> <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b></p> <p>By default, the value is selected as <b>Branch</b>.</p> </div>
<b>Currency</b>	Select the currency from the list of values.
<b>Max Withdrawal Limit Per Day</b>	Specify the maximum amount for the cash withdrawal transactions per day.
<b>No. of Transactions Per Day</b>	Specify the maximum limit for the number of cash withdrawal transactions per day.

4. Click **Save**.

The summary view is displayed with the configured details of channel limits maintenance.

## 7.6 Maintain Function Code Definitions

The **Function Code Definition** screen is used to specify the preferences for the function code.


For the list of function codes and the respective screen names, refer to [List of Function Codes](#).

To maintain function code definitions:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Function Code Definition** or specify **Function Code Definition** in the search icon bar and select the screen.


The **Function Code Definition** summary screen is displayed.

**Figure 7-11 Function Code Definition**




2. Click **Add** icon.  
The **Function Code Definition (New)** screen is displayed.

**Figure 7-12 Function Code Definition**





3. On the **Function Code Definition** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-7 Function Code Definition - Field Description**

Field	Description
<b>Function Code</b>	Select from the list function codes that are factory shipped. For the list of function codes and the respective screen names, refer to <a href="#">List of Function Codes</a> .
<b>Function Code Description</b>	Displays the description of the function code.
<b>Transaction Limit</b>	Specify the maximum transaction amount allowed for this function code in branch currency.
<b>Support Child Function Code</b>	Select if the specified function code needs to act as the parent function code.
<b>Parent Function Code</b>	Specify the applicable parent function code.  <div style="border: 1px solid #0070c0; padding: 5px; background-color: #e6f2ff;">  <b>Note:</b> This field is enabled only if the <b>Support Child Function Code</b> is not selected. </div>
<b>Next Date Transaction Allowed</b>	Select if the next day transaction posting needs to be allowed for the specified function code.
<b>Charge Details</b>	Specify the fields.
<b>Apply Charges</b>	Specify if charges are applicable for this transaction.
<b>Exchange Rate Details</b>	Specify the fields.
<b>Rate Code</b>	Select the rate code for the transaction code.
<b>Rate Type</b>	Select the rate type for the transaction code.
<b>Override Limit</b>	Specify the override limit. The system displays the default override limit currency as GBP.
<b>Stop Limit</b>	Specify the stop limit. The system displays the default stop-limit currency as GBP.
<b>Additional Preferences</b>	Specify the fields.
<b>Reversal Allowed</b>	Specify if the reversal is allowed for the transaction.
<b>Reversal Requires Authorization</b>	Specify if the authorization is required for a reversal transaction.
<b>Reversal includes charges</b>	Specify if the charges are to be reversed along with transaction reversal.
<b>Reversal Advice Name</b>	Specify the reversal advice name.
<b>Input Slip Name</b>	Specify the input slip name.

**Table 7-7 (Cont.) Function Code Definition - Field Description**

Field	Description
<b>Input Slip Confirmation</b>	<p>Select if the input slip confirmation is required for the transaction. If this option is selected for a transaction screen, the <b>Input-Slip</b> button will be displayed on the screen.</p> <p>On the specified transaction screens, you can click <b>Input-Slip</b> to view the input slip before transaction submission. Once you click <b>Input-Slip</b>, the system validates mandatory fields. In addition, you can perform any of the following actions:</p> <ul style="list-style-type: none"> <li>• <b>Confirm and Print</b> – This icon is enabled only if Input Slip Confirmation is selected in the <b>Function Code Definition</b> screen. In addition, the transaction can be submitted only if the receipt is confirmed. Click this button to confirm and print the receipt.</li> <li>• <b>Print</b> – Click <b>Print</b> to print the generated slip and provide it to the customer.</li> <li>• <b>Close</b> – Click <b>Close</b> to close the generated receipt.</li> </ul> <div style="border: 1px solid #0070C0; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>If the mandatory fields are not filled, the system shows an error message <b>Value is required</b>, wherever applicable.</p> </div>
<b>Transaction Alert Preference</b>	<p>Select the alert notification preference from the drop-down list. The values are mentioned below:</p> <ul style="list-style-type: none"> <li>• <b>Email</b> – the system sends an email notification of the transactions to the registered email ID of the customer.</li> <li>• <b>SMS</b> – the system sends an SMS notification of the transactions to the registered mobile number of the customer.</li> <li>• <b>Both</b> – the system sends SMS and email notifications of the transactions to the registered mobile number and email ID of the customer.</li> </ul> <div style="border: 1px solid #0070C0; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>The setup for Plato alerts needs to be completed and Kafka topics need to be created to enable e-mail alerts. For information on setup, refer to <i>Oracle Banking Branch Installation Guide</i>.</p> </div>
<b>Advices</b>	This section allows selecting multiple advices for the Function Code.
<b>Advice Name</b>	Select the advice name from the list of values.

4. Click **Save**.

The summary view is displayed with the configured function code definitions.

## 7.7 Maintain Branch Role Limits

The **Branch Role Limits** screen is used to set the input and authorization limits for a specific role.

Four static roles are factory-shipped and mapped with the functional activity codes. The functional activity codes maintained for each service/menu item are mapped to the respective roles. The details of each static role are provided in the table below:

**Table 7-8 Static Roles**


Static Role	Description
<b>OBBRN_BASE</b>	This role is mapped with all functional activity codes related to the service side. A user ID has to be mapped to <i>OBBRN_BASE</i> and one or more of the following roles based on the requirement: <ul style="list-style-type: none"> <li>• OBBRN_CLOUD</li> <li>• OBBRN_TELLER</li> <li>• OBBRN_VAULT</li> </ul>
<b>OBBRN_CLOUD</b>	This role is mapped with all menu-related functional activity codes, and the user can access all screens.
<b>OBBRN_TELLER</b>	This role is mapped with functional activity codes related to the menu that can be accessed by a Teller user. The user can access the screens except the following: <ul style="list-style-type: none"> <li>• All screens under Branch Maintenance</li> <li>• Open Branch Batch</li> <li>• Close Branch Batch</li> <li>• Open Vault Batch</li> <li>• Close Vault Batch</li> <li>• Buy Cash from Currency Chest</li> <li>• Sell Cash to Currency Chest</li> <li>• Interbranch Transaction Request</li> <li>• Interbranch Transaction Input</li> <li>• Interbranch Transaction Liquidation</li> </ul>
<b>OBBRN_VAULT</b>	This role is mapped with functional activity codes related to the menu that can be accessed by a Vault user. The user can access only the following screens: <ul style="list-style-type: none"> <li>• Open Vault Batch</li> <li>• Close Vault Batch</li> <li>• Buy Cash from Currency Chest</li> <li>• Sell Cash to Currency Chest</li> <li>• Interbranch Transaction Request</li> <li>• Interbranch Transaction Input</li> <li>• Interbranch Transaction Liquidation</li> </ul>

To maintain branch role limits:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Branch Role Limits** or specify **Branch Role Limits** in the search icon bar and select the screen.

The **Branch Role Limits** summary screen is displayed.


**Figure 7-13 Branch Role Limits (Summary)**



2. Click **Add** icon.

The **Branch Role Limits Maintenance** screen is displayed.

**Figure 7-14 Branch Role Limits Maintenance**



3. On the **Branch Role Limits Maintenance** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-9 Branch Role Limits Maintenance - Field Description**

Field	Description
<b>Role ID</b>	Select the role ID for which the limit preferences are to be set.
<b>Role Description</b>	Displays the role description for the selected <b>Role ID</b> .
<b>Supervisor Role</b>	Select if the defined role is a designated supervisor of the branch who has the authorization rights.



**Table 7-9 (Cont.) Branch Role Limits Maintenance - Field Description**

Field	Description
<b>Limit Currency</b>	Select the currency code in which the limits are to be specified.
<b>Input Limit</b>	Specify the transaction input limit for a single transaction.
<b>Authorization Limit</b>	Specify the maximum amount that the role is allowed to process while authorizing a transaction.
<b>Action</b>	Click the necessary icon to edit, save, or delete a row.

4. Click **Save**.

The summary view is displayed with the configured branch role limits.

## 7.8 Create Charge Pricing Maintenance

The **Create Charge Pricing Maintenance** screen is used to maintain the charge pricing.

To maintain charge pricing:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Create Charge Pricing Maintenance** or specify **Create Charge Pricing Maintenance** in the search icon bar and select the screen.

The **Create Charge Pricing Maintenance** summary screen is displayed.



**Figure 7-15 Create Charge Pricing Maintenance**

2. On the **Create Charge Pricing Maintenance** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-10 Create Charge Pricing Maintenance - Field Description**

Field	Description
<b>Application Code</b>	Specify the application code.
<b>Charge Pricing Description</b>	Specify the description of the charge pricing.

**Table 7-10 (Cont.) Create Charge Pricing Maintenance - Field Description**

Field	Description
<b>Pricing Category</b>	Select the pricing category. The drop-down list has the following values: <ul style="list-style-type: none"> <li>• <b>Fixed Amount</b></li> <li>• <b>Fixed Percent</b></li> <li>• <b>Tier Based Amount</b></li> <li>• <b>Tier Based Percent</b></li> </ul>
<b>Pricing Method</b>	Select the pricing method. The drop-down values will vary based on the <b>Pricing Category</b> .
<b>Pricing Currency</b>	Select the pricing currency.
<b>Rate Code</b>	Click the search icon and select the rate code from the list of values.
<b>Rate Type</b>	Select the rate type from the drop-down values.
<b>Charge in Transaction Currency</b>	Select if the charges are needed in the transaction currency.
<b>Min/Max Validation Criteria</b>	Select the criteria ( <b>Amount</b> or <b>Percentage</b> ) for minimum or maximum validation.
<b>Min Charge Amount/Percent</b>	Specify the minimum charge amount or percent. <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>Based on the value selected in the <b>Min/Max Validation Criteria</b>, this field gets enabled.</p> </div>
<b>Max Charge Amount/Percent</b>	Specify the minimum charge amount or percent. <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>Based on the value selected in the <b>Min/Max Validation Criteria</b>, this field gets enabled.</p> </div>

3. Click **Save**.

The summary view is displayed with the configured details of charge pricing.

## 7.9 View Charge Pricing Maintenance


The **View Charge Pricing Maintenance** screen is used to view the summary and details of charge pricing IDs.

To view charge pricing maintenance:

On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **View Charge Pricing Maintenance** or specify **View Charge Pricing Maintenance** in the search icon bar and select the screen.

The **View Charge Pricing Maintenance** is displayed.

**Figure 7-16 View Charge Pricing Maintenance**



You can view a summary of the configured records for the charge pricing details on this screen.

## 7.10 Maintain Charge Definitions


The **Charge Definition Maintenance** screen is used to maintain the charge definitions.

To maintain charge definitions:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Charge Definition Maintenance** or specify **Charge Definition Maintenance** in the search icon bar and select the screen.

The **Charge Definition Maintenance** summary screen is displayed.

**Figure 7-17 Charge Definition Maintenance (Summary)**



2. Click **Add** icon.

The **Charge Definition Maintenance (New)** screen is displayed.

**Figure 7-18 Charge Definition Maintenance (New)**

3. On the **Charge Definition Maintenance** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-11 Charge Definition Maintenance - Field Description**



Field	Description
<b>Charge Code</b>	Specify the charge code.
<b>Charge Description</b>	Specify the description of the charge code.
<b>Charge Category</b>	Select the charge category ( <b>Standard</b> or <b>Tax</b> ).
<b>Charge Credit Account</b>	Specify the charge credit account for the transaction. You can also select the GL from the list of values or the <i>DR_LEG/CR_LEG</i> .  <div style="border: 1px solid #0070C0; padding: 10px; background-color: #E6F2FF;"> <p> <b>Note:</b></p> <p>If <i>DR_LEG/CR_LEG</i> is selected, the corresponding debit/credit account of the transaction will be considered for the charge processing. For example, if the charge code is defined with <b>Charge Debit Account</b> as <i>DR_LEG</i> for a cash deposit function code, the charge will be collected from cash GL. Hence, the customer is expected to deposit cash including the charge amount. For such a charge code, the <b>Charge by Cash</b> field will be displayed as <b>Yes</b> in the charges data segment of the transaction screen.</p> </div>

Table 7-11 (Cont.) Charge Definition Maintenance - Field Description

Field	Description
<b>Charge Debit Account</b>	Specify the charge debit account for the transaction. You can also select the GL from the list of values or the <i>DR_LEG/CR_LEG</i> .  <div style="border: 1px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b></p> <p>If <i>DR_LEG/CR_LEG</i> is selected, the corresponding debit/credit account of the transaction will be considered for the charge processing. For example, if the charge code is defined with <b>Charge Debit Account</b> as <i>DR_LEG</i> for a cash deposit function code, the charge will be collected from cash GL. Hence, the customer is expected to deposit cash including the charge amount. For such a charge code, the <b>Charge by Cash</b> field will be displayed as <b>Yes</b> in the charges data segment of the transaction screen.</p> </div>
<b>Credit Txn Code</b>	Click the search icon and select the credit transaction code from the list of values.
<b>Debit Txn Code</b>	Click the search icon and select the debit transaction code from the list of values.
<b>Pricing Source System</b>	Specify the pricing source system. You can also select from the list of values.
<b>Pricing Source Description</b>	Displays the description of the pricing source.
<b>EDE Code</b>	Displays the details of charge codes added to the table.
<b>EDE Code</b>	Specify the EDE Code. You can also select from the list of values.
<b>EDE Description</b>	Displays the description of the EDE code.
<b>Action</b>	Click the necessary icon to save, edit, or delete the values of a row.

4. Click **Save**.

The summary view is displayed with the configured details of charge definitions.

## 7.11 Maintain Denomination Variance

The **Denomination Variance Maintenance** screen is used to maintain the denomination-wise variations.


In some countries, the local banking practice is to buy various FX currency denominations with different rates and lower denominations, which becomes a lower rate. This screen helps to apply rates for different denominations.

To maintain denomination variations:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Denomination Variance Maintenance** or specify **Denomination Variation Maintenance** in the search icon bar and select the screen.

The **Denomination Variance Maintenance** summary screen is displayed.


**Figure 7-19 Denomination Variance Maintenance (Summary)**



2. Click **Add** icon.

The **Denomination Variance Maintenance** screen is displayed.

**Figure 7-20 Denomination Variance Maintenance (New)**



3. On the **Denomination Variance Maintenance** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-12 Denomination Variance Maintenance - Field Description**

Field	Description
<b>Currency 1</b>	Select the currency from the list of values.
<b>Currency 2</b>	Select the currency from the list of values.

**Table 7-12 (Cont.) Denomination Variance Maintenance - Field Description**

Field	Description
<b>Maintenance Country</b>	Select the country code from the list of values.
<b>Rate Type</b>	Select the rate type from the list of values.
<b>Denomination ID</b>	Select the denomination ID from the list of values.
<b>Buy Variance</b>	Specify the buy variance.
<b>Sell Variance</b>	Specify the sell variance.

4. Click **Save**.

The summary view is displayed with the configured details of denomination-wise variations.

## 7.12 Maintain Function Code Preferences

The **Function Code Preferences** screen is used to define the workflow preferences (validation preferences and authorization preferences) for a function code.

For the list of function codes and the respective screen names, refer to [List of Function Codes](#). The rule-based authorization option in this screen is used to configure multi-level authorization with AND or OR condition. The multi-level authorization feature is described with the following example.

The sample user roles are considered as follows:

- *JUNIOR TELLER* (Supervisor enabled)
- *SENIOR TELLER1*
- *SENIOR TELLER2*
- *OFFICER LEVEL1*
- *OFFICER LEVEL2*
- *BRANCH MANAGER*

The sample values for limits and roles maintained are as below:

**Table 7-13 Sample Values for Multi-level Authorization**

Transaction Limit	Primary Authorization	Alternate Authorization
50,000 to 9,99,999	<i>SENIOR TELLER2</i> , <i>OFFICER LEVEL1</i> , and <i>OFFICER LEVEL2</i>	<i>OFFICER LEVEL2</i> and <i>BRANCH MANAGER</i>
10,00,000 to 99,99,99,999	<i>SENIOR TELLER1</i> and <i>OFFICER LEVEL1</i>	<i>OFFICER LEVEL2</i> or <i>BRANCH MANAGER</i>

The approval needs to be provided by the roles configured with AND or OR condition defined either in the primary authorization path or in the alternate authorization path. Based on the sample values provided, the following are some possible scenarios for multi-level authorization:

**Table 7-14 Examples for Multi-Level Authorization**


Condition	Authorization Process
Teller with <i>JUNIOR TELLER</i> role inputs a cash deposit transaction of amount 10,000	The transaction gets completed automatically without authorization.
Teller with <i>JUNIOR TELLER</i> role input a cash deposit of 60,000	The transaction gets assigned to all the roles mentioned in Primary and Alternate Authorization paths. For example, when a user with the <i>OFFICER LEVEL2</i> role picks the transaction and authorizes it, the transaction gets assigned to the other three roles in the Primary and Alternate paths. Further, based on the user who picks for approval, the corresponding path will be chosen by the system. If a user with <i>BRANCH MANAGER</i> Role picks the transaction for approval, the system identifies the Alternate Path for approval and ends the authorization process. If a user with <i>SENIOR TELLER2</i> role picks the transaction and authorizes, then the corresponding Primary Path will be chosen by the system for <i>OFFICER LEVEL1</i> to authorize the transaction.
Teller inputs an account transfer of 20,00,000	The transaction gets assigned to all the roles mentioned in Primary and Alternate Authorization paths. When a user with <i>BRANCH MANAGER</i> role or <i>OFFICER LEVEL2</i> role picks the transaction and authorizes it, the system identifies the path as Alternate and ends the authorization process. Else if a user with <i>OFFICER LEVEL1</i> picks the transaction and authorizes it, the system identifies the path as Primary for <i>SENIOR TELLER1</i> to authorize the transaction.

To maintain function code preferences:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Function Code Preferences** or specify **Function Code Preferences** in the search icon bar and select the screen.

The **Function Code Preferences** summary screen is displayed.

**Figure 7-21 Function Code Preferences (Summary)**





- Click **Add** icon.  
The **Function Code Preferences** screen is displayed.

**Figure 7-22 Function Code Preferences**

**Figure 7-23 Rule-Based Authorization**

General Preferences			Rule Based Authorization					Transaction Limit Check									
<input type="checkbox"/>	Currency	From Amount	<input type="checkbox"/>	Amend Charge	<input type="checkbox"/>	Amend Rate	<input type="checkbox"/>	Interbranch Transaction	<input type="checkbox"/>	Supervisor Role ID	<input type="checkbox"/>	Supervisor Role Logical Operator	<input type="checkbox"/>	Alternate Supervisor RoleID	<input type="checkbox"/>	Alternate Supervisor Role Logical...	<input type="checkbox"/>
<input type="checkbox"/>				Select C		Select C		Select One				Select One				Select One	

Page 1 of 1 (1 of 1 items) |< < 1 > >|

Figure 7-24 Transaction Limit Check

3. On the **Function Code Preferences** screen, specify the fields. For more information on fields, refer to the field description table.

Table 7-15 Function Code Preferences - Field Description






Field	Description
<b>Branch Code</b>	Select the branch code from the list of values.   <b>Note:</b> The list of values should have the *.* for the "All" option.
<b>Branch Description</b>	Displays the description of the branch code.
<b>Function Code</b>	Specify the function code. The list of values displays the valid function codes.
<b>Function Code Description</b>	Displays the description of the function code.
<b>General Preferences</b>	Specify the fields. This segment can be used to configure single-level authorization of the preferences with the use of the <b>Authorizer Role</b> field.
<b>Teller Sequence Request</b>	Select this option to generate the Teller sequence number.
<b>Teller Sequence Prefix</b>	Specify the prefix for the generation of the Teller sequence number.   <b>Note:</b> This is mandatory only if the <b>Teller Sequence Request</b> is selected.
<b>Validation Preferences</b>	Specify the fields.
<b>Charges Amendable</b>	Select if the charges are allowed to modify for the transaction.

Table 7-15 (Cont.) Function Code Preferences - Field Description

Field	Description
<b>Exchange Rate Amendable</b>	Select if the exchange rate is allowed to modify for the transaction.
<b>Rule-Based Authorization</b>	Select if the rule-based authorization is required for the transaction.  <div style="border: 1px solid #0070C0; padding: 5px; background-color: #E6F2FF;">  <b>Note:</b> Assignment mode to be defined as 'Auto' if Rule based auth flag is selected. </div>
<b>Signature Verification Required</b>	Select if the Teller needs to verify the customer's signature while submitting the transaction.
<b>Authorization Preferences</b>	Specify the fields.
<b>Authorization required for Interbranch Transaction</b>	Select if the authorization is required for the inter-branch transaction.
<b>Authorization required for Charge Amendment</b>	Select if the authorization is required in case you have amended the charge defaulted by the system.
<b>Authorization required for Exchange Rate Amendment</b>	Select if the authorization is required in case you have amended the exchange rate defaulted by the system.
<b>Authorization required by Default</b>	Select if the authorization is required by default for the transaction.
<b>Assignment Mode</b>	Select to indicate whether remote authorization assignment is the automatic or manual operation for the transaction.
<b>Authorizer Role</b>	Select the role of the authorizers. The users belonging to this role are the valid authorizers for this workflow.  <div style="border: 1px solid #0070C0; padding: 5px; background-color: #E6F2FF;">  <b>Note:</b> This field is applicable, if assignment mode is <b>Manual</b> or if assignment mode is <b>Auto</b> and no default authorizer is maintained for the user. </div>
<b>Rule-Based Authorization</b>	Specify the fields. This segment can be used to configure multi-level authorization of the preferences with the use of <b>Supervisor Role ID</b> and <b>Alternate Supervisor Role ID</b> fields.  <div style="border: 1px solid #0070C0; padding: 5px; background-color: #E6F2FF;">  <b>Note:</b> Rule Based Authorization cannot be applied for customer servicing transactions. </div>

**Table 7-15 (Cont.) Function Code Preferences - Field Description**

Field	Description
<b>Currency</b>	Select the currency of the transaction from the LOV.
<b>From Amount</b>	Specify the "From" cap amount.
<b>To Amount</b>	Specify the "To" cap amount.
<b>Amend Charge</b>	Select from the drop-down values ( <b>Yes, No</b> or <b>Both</b> ).
<b>Amend Rate</b>	Select from the drop-down values ( <b>Yes, No</b> or <b>Both</b> ).
<b>Interbranch Transaction</b>	Select from the drop-down values ( <b>Yes, No</b> or <b>Both</b> ).
<b>Supervisor Role ID</b>	Select the supervisor role ID from the list of values. The following conditions apply to this field: <ul style="list-style-type: none"> <li>• More than one can be added for authorization.</li> <li>• If multiple roles are added, it is not mandatory to authorize in sequential order of the roles added.</li> <li>• The roles added in this field are considered for the primary level of authorization.</li> </ul>
<b>Supervisor Role Logical Operator</b>	Select the logical operator AND or OR. If AND is chosen, all the Supervisor role specified in primary path has to authorize the transaction. If OR is chosen, either of the Supervisor role has to authorize the transaction.
<b>Alternate Supervisor Role ID</b>	Select the alternate role ID from the list of values. The following conditions apply to this field: <ul style="list-style-type: none"> <li>• More than one role can be added for authorization.</li> <li>• If multiple roles are added, it is not mandatory to authorize in sequential order of the roles added.</li> <li>• The roles added in this field are considered for the secondary level of authorization.</li> </ul>
<b>Alternate Supervisor Role Logical Operator</b>	Select the logical operator AND or OR. If AND is chosen, all the Supervisor role specified in primary path has to authorize the transaction. If OR is chosen, either of the Supervisor role has to authorize the transaction.
<b>Transaction Limit Check</b>	Specify the details under this section. Double-click on a row to enable the fields.
<b>Transaction Currency</b>	Click the search icon, and select the transaction currency from the list of values.
<b>Transaction Amount</b>	Specify the transaction amount.
<b>Action</b>	Click the necessary icon to save, edit, or delete the values of a row.

4. Click **Save**.

The summary view is displayed with the configured function code preferences.

## 7.13 Maintain Accounting and Settlements


The **Settlements Definition** screen is used to define the settlement and accounting parameters that are applicable for processing the branch transactions involving a function code.

To maintain accounting and settlements:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Settlements Definition** or specify **Settlements Definition** in the search icon bar and select the screen.

The **Settlements Definition** summary screen is displayed.


**Figure 7-25 Settlements Definition (Summary)**



2. Click **Add** icon.

The **Accounting Settlement** screen is displayed.

**Figure 7-26 Accounting Settlement**



3. On the **Accounting Settlement** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-16 Accounting Settlement - Field Description**








Field	Description
<b>Function Code</b>	Select the function code for which the accounting details need to be defined from the list of values.
<b>Function Code Description</b>	Displays the description of the selected function code.
<b>Branch</b>	Select the branch for which the accounting details need to be defined from the list of values.  <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b> The value *.* indicates the "All" option.</p> </div>
<b>Currency</b>	Select the currency for which the accounting details need to be defined from the list of values.  <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b> The value *.* indicates the "All" option.</p> </div>
<b>Transaction Account/GL</b>	Select the transaction account or GL from the list of values. The list of values displays all valid GLs maintained. This field is kept blank if the transaction account needs to be selected from the transaction screen.  <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b> LOV query will fetch the Nostro type of accounts for 9009 and 9010 function codes. For other function codes, only GL accounts will be fetched from LOV.</p> </div>
<b>Offset Account/GL No</b>	Select the offset account or GL from the list of values. The list of values displays all valid GLs maintained.  <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b> LOV query will fetch the Nostro type of accounts for 9009 and 9010 function codes. For other function codes, only GL accounts will be fetched from LOV.</p> </div>
<b>Transaction Code for Debit</b>	Select the transaction code used for debit accounting from the list of values.
<b>Transaction Code for Credit</b>	Select the transaction code used for credit accounting from the list of values.

Table 7-16 (Cont.) Accounting Settlement - Field Description

Field	Description
<b>Main Leg Accounting Required</b>	Select to pass the main accounting entries along with the charges defined in the transaction code.
<b>Netting Charge Required</b>	 <b>Note:</b> This field is meant for future use.
<b>Profit Reval GL</b>	Specify the profit revaluation GL details.   <b>Note:</b> This field is used during accounting only when the transaction involves negotiated exchange rate.
<b>Loss Reval GL</b>	Specify the loss revaluation GL details.   <b>Note:</b> This field is used during accounting only when the transaction involves negotiated exchange rate.

4. Click **Save**.

The summary view is displayed with the configured accounting details.

## 7.14 Maintain Reject Codes

The **Reject Code Maintenance** screen is used to maintain the reject codes.


The reject codes maintained in this screen are used to reject the check withdrawal transactions with the appropriate reject code.

To maintain reject codes:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Reject Code Maintenance** or specify **Reject Code Maintenance** in the search icon bar and select the screen.


The **Reject Code Maintenance** summary screen is displayed.

**Figure 7-27 Reject Code Maintenance (Summary)**



2. Click **Add** icon.  
The **Reject Code Maintenance** screen is displayed.

**Figure 7-28 Reject Code Maintenance (New)**



3. On the **Reject Code Maintenance** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-17 Reject Code Maintenance - Field Description**

Field	Description
<b>Reject Code</b>	Specify the reject code. This code indicates the reason for rejecting a clearing transaction.
<b>Reject Code Description</b>	Specify the description of the reject code.
<b>Applicable For</b>	Select from the radio list from the following drop-down values: <ul style="list-style-type: none"> <li>• <b>Inward Return</b></li> <li>• <b>Outward Return</b></li> <li>• <b>Both Inward and Outward Return</b></li> <li>• <b>Inhouse Checks</b></li> </ul>

4. Click **Save**.  
The summary view is displayed with the configured details of reject codes.



## 7.15 Maintain Account Group


The **Account Group Maintenance** screen is used to create groups of the account codes, and these groups can be used for charge calculation.

To maintain account group:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Account Group Maintenance** or specify **Account Group Maintenance** in the search icon bar and select the screen.

The **Account Group Maintenance** summary screen is displayed.


**Figure 7-29 Account Group Maintenance (Summary)**



2. Click **Add** icon.

The **Account Group Maintenance (New)** screen is displayed.

**Figure 7-30 Account Group Maintenance (New)**



- On the **Account Group Maintenance** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-18 Account Group Maintenance - Field Description**

Field	Description
<b>Account Group Code</b>	Specify the account group code.
<b>Account Group Code Description</b>	Specify the description of the account group code.
<b>Add Accounts</b>	Specify the fields.
<b>Account Number</b>	Specify the account number. You can also select from the list of values.
<b>Account Group Code</b>	Displays the account group code.
<b>Action</b>	Click the necessary icon to save, edit, or delete the values of a row.

- Click **Save**.

The summary view is displayed with the configured details of account groups.

## 7.16 Maintain External System

The **External System Maintenance** screen is used to define the parameters for the external system.


The parameters are defined whenever there is an external system call to the Oracle Banking Branch external API. Only the registered users can make the external system call to process the transaction.

To maintain external system:

- On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **External System Maintenance** or specify **External System Maintenance** in the search icon bar and select the screen.

The **External System Maintenance** summary screen is displayed.

**Figure 7-31 External System Maintenance (Summary)**



- Click **Add** icon.  
The **External System Maintenance (New)** screen is displayed.



**Figure 7-32 External System Maintenance (New)**

- On the **External System Maintenance** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-19 External System Maintenance - Field Description**

Field	Description
<b>External System Code</b>	Specify the system code of the registered external system.
<b>External System Name</b>	Specify the name of the registered external system.
<b>Function Code</b>	Specify the function code of the transaction, which needs to be performed through the external system. You can also select from the list of values.
<b>On Warning</b>	Select from the drop-down list. The values in the drop-down list are mentioned below: <ul style="list-style-type: none"> <li><b>Ignore</b> – Select if you need to ignore the override raised and process the transaction until completion.</li> <li><b>Error</b> – Select if you need to show the error message and stop the transaction.</li> </ul>
<b>On Approval</b>	Select from the drop-down list. The values in the drop-down list are mentioned below: <ul style="list-style-type: none"> <li><b>Ignore</b> – Select if you need to ignore the override raised and process the transaction until completion.</li> <li><b>Error</b> – Select if you need to show the error message and stop the transaction.</li> </ul>

**Table 7-19 (Cont.) External System Maintenance - Field Description**

Field	Description
<b>Incoming User Type</b>	<p>Select the incoming user type from the drop-down values. The values in the drop-down list are mentioned below:</p> <ul style="list-style-type: none"> <li>• <b>User</b> – User appearing in the payload to process the transaction.</li> <li>• <b>Default User</b> – Default user that is maintained to process the transaction.</li> <li>• <b>Role</b> – Role appearing in the payload to process the transaction.</li> <li>• <b>Default Role</b> – Default role that is maintained to process the transaction.</li> </ul>
<b>Default User</b>	<p>Specify the default user maintained.</p> <div style="border: 1px solid #ccc; background-color: #e6f2ff; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>This field is applicable only if the <b>Incoming User Type</b> is selected as <b>Default User</b>.</p> </div>
<b>Default Role</b>	<p>Specify the default role maintained.</p> <div style="border: 1px solid #ccc; background-color: #e6f2ff; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>This field is applicable only if the <b>Incoming User Type</b> is selected as <b>Default Role</b>.</p> </div>
<b>External Initiation</b>	<p>Select if you need to log the transaction into Journal Log with the status <b>Initiated</b>.</p>
<b>Till Update</b>	<p>Select if you need to update the Till.</p>
<b>Authorization required by Default</b>	<p>Select if you need to raise an override even if it is <b>N</b> in function preference.</p>
<b>Action</b>	<p>Click the necessary icon to edit, save, or delete a row.</p>

4. Click **Save**.

The summary view is displayed with the configured details of external system maintenance.

## 7.17 Maintain External Bank Codes


The **External Bank Code** screen is used to maintain the bank codes and branch codes.

To maintain external bank codes:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **External Bank Code** or specify **External Bank Code** in the search icon bar and select the screen.

The **External Bank Code** summary screen is displayed.


**Figure 7-33 External Bank Code (Summary)**



2. Click **Add** icon.

The **External Bank Code** screen is displayed.

**Figure 7-34 External Bank Code (New)**



3. On the **External Bank Code** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-20 External Bank Code - Field Description**

Field	Description
<b>Bank Code</b>	Specify the bank code.
<b>Bank Name</b>	Specify the name of the bank.
<b>Branch Code</b>	Specify the branch code.
<b>Branch Name</b>	Specify the branch name.
<b>Branch Address 1 to Branch Address 4</b>	Specify the address of the branch.

4. Click **Save**.

The summary view is displayed with the configured details of external bank and branch codes.

## 7.18 Maintain Charge Decisions

The **Charge Decision Maintenance** screen is used to maintain the charge decisions.

To maintain charge decisions:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Charge Decision Maintenance** or specify **Charge Decision Maintenance** in the search icon bar and select the screen.

The **Charge Decision Maintenance** summary screen is displayed.

**Figure 7-35 Charge Decision Maintenance (Summary)**


2. Click **Add** icon.

The **Charge Decision Maintenance** screen is displayed.

**Figure 7-36 Charge Decision Maintenance (New)**

3. On the **Charge Decision Maintenance** screen, specify the fields. For more information on fields, refer to the field description table.

Table 7-21 Charge Decision Maintenance - Field Description

Field	Description
<b>Function Code</b>	Specify the function code. You can also select from the list of values.
<b>Branch</b>	Specify the branch code. You can also select from the list of values.
<b>Currency</b>	Specify the currency code. You can also select from the list of values.
<b>Inter Branch</b>	Select the inter-branch requirement from the following drop-down values: <ul style="list-style-type: none"> <li>• <b>Yes</b></li> <li>• <b>No</b></li> <li>• <b>Both</b></li> </ul>
<b>Charge Details</b>	Specify the fields.
<b>Charge Code</b>	Specify the charge code. You can also select from the list of values.
<b>Charge Description</b>	Displays the description of the charge code specified.
<b>Charge Pricing Rule ID</b>	Specify the charge-pricing rule ID. You can also select from the list of values. <div style="border-left: 2px solid #0070C0; border-right: 2px solid #0070C0; border-bottom: 2px solid #0070C0; padding: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>You can choose the pricing rule ID to apply charge or choose a group code from which the pricing rule will be picked for calculation. You can only define the rule or group. Either the rule can be used, or a group can be used.</p> </div>
<b>Charge Pricing Rule Description</b>	Displays the description of the charge-pricing rule ID specified.
<b>Charge Basis</b>	Specify the charge basis. You can also select from the list of values.
<b>Charge Condition Group</b>	Specify the charge condition group. You can also select from the list of values.
<b>Action</b>	Click the necessary icon to save, edit, or delete the values of a row.

4. Click **Save**.

The summary view is displayed with the configured details of charge decisions.

## 7.19 Maintain Charge Condition Group


The **Charge Condition Group Maintenance** screen is used to create groups of the charge condition codes.

To maintain charge condition group:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Charge Condition Group Maintenance** or specify **Charge Condition Group Maintenance** in the search icon bar and select the screen.

The **Charge Condition Group Maintenance** summary screen is displayed.


**Figure 7-37 Charge Condition Group Maintenance (Summary)**



2. Click **Add** icon.

The **Charge Condition Group Maintenance** screen is displayed.

**Figure 7-38 Charge Condition Group Maintenance (New)**



3. On the **Charge Condition Group Maintenance** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-22 Charge Condition Group Maintenance - Field Description**

Field	Description
<b>Charge Condition Group Code</b>	Specify the charge group code.
<b>Charge Condition Group Code Description</b>	Specify the description of the charge group code.



Table 7-22 (Cont.) Charge Condition Group Maintenance - Field Description

Field	Description
<b>Parameter 1 to Parameter 5</b>	Select the parameters 1 to 5. For more information on Parameters, refer to <a href="#">Additional Information on Parameters</a> .
<b>Charge Details</b>	Specify the fields.
<b>Value 1 to Value 5</b>	Specify the values 1 to 5. You can also select from the list of values.
<b>Charge Pricing Rule ID</b>	Specify the charge pricing rule ID. You can also select from the list of values.
<b>Charge Pricing Rule Description</b>	Displays the description for specified charge pricing rule ID.
<b>Reset</b>	Click <b>Reset</b> to reset the charge group details added.
<b>Add Charge Group</b>	Click <b>Add Charge Group</b> to add the charge group details specified.
<b>Charge Groups Added</b>	Displays the details of charge groups added to the table.

4. Click **Save**.

The summary view is displayed with the configured groups of the charge condition codes.

- [Additional Information on Parameters](#)

The **Parameters** field on the **Charge Condition Group Maintenance** screen needs to be selected based on the specified conditions.

## 7.19.1 Additional Information on Parameters

The **Parameters** field on the **Charge Condition Group Maintenance** screen needs to be selected based on the specified conditions.

There will be a few parameters like Customer Group, Account Group, or Branch group will be pre-shipped. Customers need to choose the parameters, group them, and name them with the group codes. A rule will be attached to the group code so that based on the group used corresponding rule will be applied for calculation.

If the Charge Condition Group Maintenance is made with a specific parameter, the CHG\_PARAM\_TAGS column in the SRV\_TB\_TX\_STATIC\_TAGS table of transaction schema needs to be updated. For example, if Parameter 1 is selected as a utility provider, it needs to be updated as below:

```
{
  "UtilityProvider": "$.institutionID",
  "P2": "",
  "P3": "",
  "P4": "",
  "P5": ""
}
```

For the other options in **Parameter** field, the JSON needs to be updated as follows:

**Table 7-23 Options for Parameter Fields**

Option	Value
<b>Account Group</b>	"AccountGroup": ""
<b>Customer Group</b>	"CustomerGroup": ""
<b>Transaction Branch Group</b>	"TransactionBranchGroup": ""
<b>To Account Branch Group</b>	"ToAccountBranchGroup": ""
<b>To Account Branch</b>	"ToAccountBranch": "\$.toAccountBranch" <\$.toAccountBranch has to be replaced with the field id as per the FID that captures To Account Branch>
<b>Account Currency</b>	"AccCcy": "\$.AccCcy" <\$.AccCcy has to be replaced with the field id as per the FID that captures Account Currency>
<b>Utility Provider</b>	"UtilityProvider": "\$.institutionID" <\$.institutionID has to be replaced with the field id as per the FID that captures Utility Provider>

## 7.20 Maintain Customer Group


The **Customer Group Maintenance** screen is used to create groups of the customer codes, and these groups can be used for charge calculation.

To maintain customer group:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Customer Group Maintenance** or specify **Customer Group Maintenance** in the search icon bar and select the screen.

The **Customer Group Maintenance** summary screen is displayed.

**Figure 7-39 Customer Group Maintenance (Summary)**




2. Click **Add** icon.

The **Customer Group Maintenance (New)** screen is displayed.

**Figure 7-40 Customer Group Maintenance (New)**

3. On the **Customer Group Maintenance** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-24 Customer Group Maintenance - Field Description**

Field	Description
<b>Customer Group Code</b>	Specify the customer group code.
<b>Customer Group Code Description</b>	Specify the description of the customer group code.
<b>Customers Added</b>	Displays the details of customer numbers added to the table.
<b>Customer Number</b>	Specify the customer number. You can also select from the list of values.  <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>You cannot add the same customer number in two different groups.</p> </div>
<b>Customer Name</b>	Displays the description for the specified customer number.
<b>Actions</b>	Click the necessary icon to save, edit, or delete the values of a row.

4. Click **Save**.

The summary view is displayed with the configured details of customer groups.

## 7.21 Maintain Default Authorizer

The **Default Authorizer** screen is used to define the default authorizer who can authorize a specific function code for a branch user.


Once it is defined, the system automatically routes the transactions of this function code to the default authorizer defined for the branch user.

To maintain default authorizer:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Default Authorizer** or specify **Default Authorizer** in the search icon bar and select the screen.

The **Default Authorizer** summary screen is displayed.


**Figure 7-41 Default Authorizer (Summary)**



2. Click **Add** icon.


The **Default Authorizer (New)** screen is displayed.

**Figure 7-42 Default Authorizer**



3. On the **Default Authorizer** screen, specify the fields. For more information on fields, refer to the field description table.

Table 7-25 Default Authorizer - Field Description

Field	Description
<b>User ID</b>	Select the user ID from the list of values. The list consists of user IDs for which a default authorizer needs to be maintained.
<b>User Name</b>	Displays the name of the user, when you select the user ID.
<b>Branch Code</b>	Select the branch code from the list of values. This field is enabled if the <b>All</b> option is selected in the <b>User ID</b> field.  <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-left: 20px;"> <p> <b>Note:</b></p> <p>If a specific authorizer is selected, then the system will default the home branch as branch code.</p> </div>
<b>Branch Name</b>	Displays the branch name, when you select the <b>Branch Code</b> .
<b>Default Authorizer</b>	Select the default authorizer from the list of values, if it is already set while assigning the transaction. If the mode assigned is <b>Manual</b> , it allows changing the default authorizer.  Select the authorizer ID from the adjoining option list. The options list consists of authorizers who are mapped to a role with <b>Savings Authorizer</b> flag value as <b>Y</b> or <b>All</b> option.
<b>Description</b>	Displays the description.

4. Click **Save**.

The summary view is displayed with the configured default authorizer.

## 7.22 Maintain Branch Group


The **Branch Group Maintenance** screen is used to create groups of the branch codes, and these groups can be used for charge calculation.

To maintain branch group:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Branch Group Maintenance** or specify **Branch Group Maintenance** in the search icon bar and select the screen.


The **Branch Group Maintenance** summary screen is displayed.

**Figure 7-43 Branch Group Maintenance (Summary)**



2. Click **Add** icon.  
The **Branch Group Maintenance (New)** screen is displayed.

**Figure 7-44 Branch Group Maintenance (New)**



3. On the **Branch Group Maintenance** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-26 Branch Group Maintenance - Field Description**

Field	Description
<b>Branch Group Code</b>	Specify the branch group code.
<b>Branch Group Code Description</b>	Specify the description of the branch group code.
<b>Add Branch</b>	Specify the fields.
<b>Branch Code</b>	Specify the branch code. You can also select from the list of values.
<b>Branch Group Code</b>	Displays the description for the specified branch code.
<b>Action</b>	Click the necessary icon to save, edit, or delete the values of a row.

4. Click **Save**.

The summary view is displayed with the configured details of branch groups.

## 7.23 Static Data

The **Static Data** screen is to populate the data for the static widgets.

The following static widgets can be populated with the **Static Data** screen:

- Alerts
- Notifications
- Frequent Branch Operations
- Frequent Customer Operations
- Frequent Links
- Customer Service Request

To populate the data for the widgets:

1. On the **Home** screen, from **Teller** mega menu, under **Branch Maintenance**, click **Static Data** or specify **Static Data** in the search icon bar and select the screen.

The **Static Data** screen is displayed.

**Figure 7-45 Static Data**

The screenshot shows the 'Static Data' screen with a light gray background and a pattern of overlapping circles. At the top left, the title 'Static Data' is displayed. Below the title are four input fields arranged in a 2x2 grid. The top-left field is labeled 'User Id' and has a search icon and 'Required' text below it. The top-right field is labeled 'Branch Code' and also has a search icon and 'Required' text. The bottom-left field is labeled 'Branch date' and has a calendar icon and 'Required' text. The bottom-right field is labeled 'Narrative' and has 'Required' text. A 'Submit' button is located at the bottom left of the form area.

2. On the **Static Data** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 7-27 Static Data - Field Description**

Field	Description
<b>User Id</b>	Select the user name from the list of values.
<b>Branch Code</b>	Select the branch code from the list of values.
<b>Branch Date</b>	Select the branch date.
<b>Narrative</b>	Specify the description.

3. Click **Submit**.

# 8

## Till-Vault Operations

The Vault Teller or Teller can use Till-Vault operations to monitor the cash and currency boxes for the day. It is also used to perform cash transfers from or to the Vault/Till.

This topic contains the following subtopics:

- [Buy Cash from Vault](#)  
The Teller can use the **Buy Cash from Vault** screen to get cash from the vault.
- [Buy Cash from Till](#)  
The Teller can use this screen to transfer cash from another Teller in case of insufficient funds available in the till to perform the customer cash transactions.
- [Buy Cash from Currency Chest](#)  
The Vault Teller can use this screen to get cash from the currency chest after opening the vault batch and deposit it into the vault. Once the cash is transferred from the currency chest, the system updates the cash position.
- [Sell Cash to Currency Chest](#)  
The Vault Teller can use this screen to sell cash to the Central Bank from the vault after all the Tellers have sold the additional cash to the Vault Teller.
- [Sell Cash to Till](#)  
The Teller can use the **Sell Cash to Till** screen to transfer cash to another Teller's Till in case of excess funds available in the Till.
- [Denomination Exchange](#)  
The Teller can use the **Denomination Exchange** screen to exchange the currency denominations.
- [Sell Cash to Vault](#)  
The Teller can use the **Sell Cash to Vault** screen to sell cash to the vault. It is used only when the *cash held* exceeds the limit set at the template level for any currency.
- [Inter Branch Transactions](#)  
The interbranch transactions are used to send a request from a bank branch to the central cash depository, for pickup or delivery of cash.

### 8.1 Buy Cash from Vault

The Teller can use the **Buy Cash from Vault** screen to get cash from the vault.

To get cash from the vault:

1. On the **Home** screen, from **Teller** mega menu, under **Till-Vault Operations**, click **Buy Cash from Vault** or specify **Buy Cash from Vault** in the search icon bar and select the screen.

The **Buy Cash from Vault** screen is displayed.



**Figure 8-1 Buy Cash from Vault**

2. On the **Buy Cash from Vault** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 8-1 Buy Cash from Vault - Field Description**

Field	Description
<b>Total Required Cash</b>	Specify the total cash that you need to transfer from the vault to the till of the logged-in Teller.  <div style="border: 1px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b> By default, the system displays the local currency of the branch. The user can select another currency from the drop-down values in which cash needs to be transferred from the vault.</p> </div>
<b>Narrative</b>	Displays the default narrative as <b>Transfer Cash from Vault</b> , and it can be modified.

3. Specify the denomination details. For information on the fields in the **Denomination** segment, refer to [Add Denomination Details](#).
4. Click **Submit**.

A teller sequence number is generated, and the `Transaction Completed Successfully` information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any warning raised when the transaction saves. On transaction completion, the accounting entries (for example, Dr Teller Cash GL & Cr Vault Cash GL) for the transaction will be handed off to accounting based on the settlement definition maintained for the function code. Also, the cash positions of the Teller are increased and the Vault Teller is decreased successfully.

If the cash position of the Vault Teller is less than the total cash requested by the Teller:

- The system displays an error message
- The Teller needs to perform this transaction after the vault is replenished sufficiently

## 8.2 Buy Cash from Till

The Teller can use this screen to transfer cash from another Teller in case of insufficient funds available in the till to perform the customer cash transactions.


Teller can request the required cash in a specific currency, and on completing this transaction, the system updates the cash position of both the Tellers to the extent of the transaction amount.

To transfer cash from another Teller's till:

1. On the **Home** screen, from **Teller** mega menu, under **Till-Vault Operations**, click **Buy Cash from Till** or specify **Buy Cash from Till** in the search icon bar and select the screen.

The **Buy Cash from Till** screen is displayed.

**Figure 8-2 Buy Cash from Till**



Teller Transaction - Transfer Cash from Till to Till Branch Date - Mar 30, 2018

Buy Cash from Till

Teller ID  Required Total Required Cash


Required GBP  Required

Narrative

Denomination

2. On the **Buy Cash from Till** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 8-2 Buy Cash from Till - Field Description**

Field	Description
<b>Teller ID</b>	Displays the Teller ID from where the cash needs to be transferred.
<b>Total Required Cash</b>	Specify the total cash that you need to transfer from the specified <b>Teller ID</b> to the till of logged-in Teller.  <div style="border: 1px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b></p> <p>By default, the system displays the local currency of the branch. You can select another currency from the drop-down values in which cash needs to be transferred.</p> </div>
<b>Narrative</b>	Displays the default narrative as <b>Transfer Cash from Till</b> , and it can be modified.

3. Specify the denomination details. For information on the fields in the **Denomination** segment, refer to [Add Denomination Details](#).
4. Click **Submit**.

A teller sequence number is generated, and the `Transaction Completed Successfully` information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any warning raised when the transaction saves. On transaction completion, the cash balance of both the Tellers is updated successfully.

## 8.3 Buy Cash from Currency Chest

The Vault Teller can use this screen to get cash from the currency chest after opening the vault batch and deposit it into the vault. Once the cash is transferred from the currency chest, the system updates the cash position.

To buy cash from the currency chest:

1. On the **Home** screen, from **Teller** mega menu, under **Till-Vault Operations**, click **Buy Cash from Ccy Chest**.

The **Buy Cash from Currency Chest** screen is displayed.

**Figure 8-3 Buy Cash from Currency Chest**

2. On the **Buy Cash from Currency Chest** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 8-3 Buy Cash from Currency Chest - Field Description**

Field	Description
<b>Total Required Cash</b>	Specify the total cash that you need to buy from Currency Chest.  <div style="border: 1px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b> By default, the system displays the local currency of the branch. You can select another currency from the drop-down values in which cash needs to be bought from the currency chest.</p> </div>
<b>Narrative</b>	Displays the default narrative <code>Buy Cash from Currency Chest</code> , and it can be modified.

3. Specify the denomination details. For information on the fields in the **Denomination** segment, refer to [Add Denomination Details](#).
4. Click **Submit**.

A teller sequence number is generated, and the `Transaction Completed Successfully` information message is displayed.

**Note:**

The transaction is moved to authorization in case of any warning raised when the transaction saves. On transaction completion, the cash balance of the Vault Teller is updated successfully.

## 8.4 Sell Cash to Currency Chest

The Vault Teller can use this screen to sell cash to the Central Bank from the vault after all the Tellers have sold the additional cash to the Vault Teller.

The Vault Teller can close the batch only if the excess cash is not available at the end of the day.

To sell cash to currency chest:

1. On the **Home** screen, from **Teller** mega menu, under **Till-Vault Operations**, click **Sell Cash to Ccy Chest** or specify **Sell Cash to Ccy Chest** in the search icon bar and select the screen.

The **Sell Cash to Currency Chest** screen is displayed.

**Figure 8-4 Sell Cash to Currency Chest**

2. On the **Sell Cash to Currency Chest** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 8-4 Sell Cash to Currency Chest - Field Description**

Field	Description
<b>Total Required Cash</b>	Specify the total cash that you need to sell to the Currency Chest.  <div style="border: 1px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b> By default, the system displays the local currency of the branch. The user can select another currency from the drop-down values in which cash needs to be sold to the currency chest.</p> </div>
<b>Narrative</b>	Displays the default narrative <code>Sell Cash to Currency Chest</code> , and it can be modified.

3. Specify the denomination details. For information on the fields in the **Denomination** segment, refer to [Add Denomination Details](#).

4. Click **Submit**.

A teller sequence number is generated, and the `Transaction Completed Successfully` information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any warning raised when the transaction saves. On transaction completion, the cash balance of the Vault Teller is updated successfully.

## 8.5 Sell Cash to Till

The Teller can use the **Sell Cash to Till** screen to transfer cash to another Teller's Till in case of excess funds available in the Till.


In addition, the Teller can request to transfer from the Till in a specific currency. Once the transaction is completed, the system updates the cash position of both the Tellers to the extent of the transaction amount.

To sell cash to the Till:

1. On the **Home** screen, from **Teller** mega menu, under **Till-Vault Operations**, click **Sell Cash to Till** or specify **Sell Cash to Till** in the search icon bar and select the screen.

The **Sell Cash to Till** screen is displayed.

**Figure 8-5 Sell Cash to Till**




2. On the **Sell Cash to Till** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 8-5 Sell Cash to Till - Field Description**

Field	Description
Teller ID	Displays the <b>Teller ID</b> from which the cash needs to be transferred.

**Table 8-5 (Cont.) Sell Cash to Till - Field Description**

Field	Description
<b>Total Required Cash</b>	Specify the total cash that you need to transfer to the specified <b>Teller ID</b> from the till of the logged-in Teller.  <div style="border-left: 2px solid #0070C0; padding-left: 10px; background-color: #E6F2FF;"> <p> <b>Note:</b></p> <p>By default, the system displays the local currency of the branch. The user can select another currency from the drop-down values in which the cash needs to be transferred.</p> </div>
<b>Narrative</b>	Displays the default narrative as <b>Transfer Cash to Till</b> , and it can be modified.

3. Specify the denomination details. For information on the fields in the **Denomination** segment, refer to [Add Denomination Details](#).
4. Click **Submit**.

A teller sequence number is generated, and the `Transaction Completed Successfully` information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any warning raised when the transaction saves. On transaction completion, the cash balance of both the Tellers is updated successfully.

## 8.6 Denomination Exchange

The Teller can use the **Denomination Exchange** screen to exchange the currency denominations.

The exchange can be performed for the internal purpose of the bank or based on the customer's request. The outgoing cash needs to be entered as negative in the denomination details segment. This transaction involves only denomination exchange from the Till. The total value in the Till remains the same, and accounting entries are not posted for this exchange. However, the denomination count in the Till changes, and hence it needs to be updated.

To exchange the currency denominations:

1. On the **Home** screen, from **Teller** mega menu, under **Till-Vault Operations**, click **Denomination Exchange** or specify **Denomination Exchange** in the search icon bar and select the screen.

The **Denomination Exchange** screen is displayed.

Figure 8-6 Denomination Exchange

2. On the **Denomination Exchange** screen, specify the fields. For more information on fields, refer to the field description table.

Table 8-6 Denomination Exchange - Field Description

Field	Description
<b>Branch Code</b>	Displays the logged-in branch code.
<b>Transaction Currency</b>	Specify the currency for which the denominations are to be exchanged.

3. Specify the denomination details. For information on the fields in the **Denomination** segment, refer to [Add Denomination Details](#).
4. Click **Submit**.

A teller sequence number is generated, and the `Transaction Completed Successfully` information message is displayed.

 **Note:**

The transaction is moved to authorization in case of any warning raised when the transaction saves. On transaction completion, the cash balance of both the Tellers is updated successfully.

## 8.7 Sell Cash to Vault

The Teller can use the **Sell Cash to Vault** screen to sell cash to the vault. It is used only when the *cash held* exceeds the limit set at the template level for any currency.

For transferring cash to the vault, the Teller batch and the Vault batch need to be opened for the posting date.

To sell cash to the vault:

1. On the **Home** screen, from **Teller** mega menu, under **Till-Vault Operations**, click **Sell Cash to Vault** or specify **Sell Cash to Vault** in the search icon bar and select the screen. The **Sell Cash to Vault** screen is displayed.



**Figure 8-7 Sell Cash to Vault**

2. On the **Sell Cash to Vault** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 8-7 Sell Cash to Vault - Field Description**

Field	Description
<b>Total Required Cash</b>	Specify the total cash that you need to transfer to the vault from the till of the logged-in Teller.  <div style="border: 1px solid #0070C0; padding: 5px; background-color: #E6F2FF;"> <p> <b>Note:</b> By default, the system displays the local currency of the branch. The user can select another currency from the drop-down values in which cash needs to be transferred to the vault.</p> </div>
<b>Narrative</b>	Displays the default narrative as <b>Transfer Cash to Vault</b> , and it can be modified.

3. Specify the denomination details. For information on the fields in the **Denomination** segment, refer to [Add Denomination Details](#).
4. Click **Submit**.

A teller sequence number is generated, and the `Transaction Completed Successfully` information message is displayed.

**Note:**

The transaction is moved to authorization in case of any warning raised when the transaction saves. On transaction completion, the accounting entries (for example, Dr Vault Cash GL & Cr Teller Cash GL) for the transaction will be handed off to accounting based on the settlement definition maintained for the function code. Also, the cash balance of the Teller is decreased and the Vault Teller is increased successfully.

## 8.8 Inter Branch Transactions

The interbranch transactions are used to send a request from a bank branch to the central cash depository, for pickup or delivery of cash.

A branch can request delivery of cash when it is having a shortage of cash and request for pickup of cash when it has excess cash. The process steps to request cash delivery and pickup are explained below.

The process steps for cash delivery are as follows:

1. The requesting branch sends a request for delivery of cash using the 1409 screen.
2. The remitting branch queries for the requests and accepts the request using the 1409 screen.
3. On the delivery date, the remitting branch books a transaction using the 1410 screen with the denominations being sent and generated.
4. On the delivery date, the remitting branch books a transaction input using the 1410 screen, generates advice, and sends money to the requesting branch.
5. On receiving money and advice, the requesting branch uses the 1411 screen to verify the denominations and save the liquidation.

The process steps for cash pickup are as follows:

1. The requesting branch sends a request for the pickup of cash using the 1409 screen.
2. The receiving branch queries for the requests and accepts the request using the 1409 screen.
3. On the date of cash pickup, the receiving branch generates advice and sends it to requesting branch.
4. The requesting branch receives the advice and books the transaction using the 1410 screen.
5. The requesting branch generates the advice and sends money and advice to the receiving branch.
6. The receiving branch receives the money and advice and verifies and liquidates the request using the 1411 screen.



### Note:

Accounting entries are not passed for the 1409 screen.

This topic contains the following subtopics:

- [Inter Branch Transaction Request](#)  
The **Inter Branch Transaction Request** screen is used to create the inter-branch cash pickup or cash delivery requests. When a branch needs cash, the branch can request a cash delivery and when the branch has excess cash, the branch can request cash pickup.
- [Inter Branch Transaction Input](#)  
The **Inter Branch Transaction Input** screen is used for a branch to act as a remitting branch to book an input transaction for cash delivery.

- [Inter Branch Transaction Liquidation](#)  
The receiving branch can use the **Inter Branch Transaction Liquidation** screen to receive the cash by way of cash delivery or cash pickup, verify the advice with denomination units, and liquidate the request.

## 8.8.1 Inter Branch Transaction Request

The **Inter Branch Transaction Request** screen is used to create the inter-branch cash pickup or cash delivery requests. When a branch needs cash, the branch can request a cash delivery and when the branch has excess cash, the branch can request cash pickup.

To create the inter-branch transaction request:

1. On the **Home** screen, from **Teller** mega menu, under **Till-Vault Operations**, click **Inter Branch Txn Req** or specify **Inter Branch Txn Req** in the search icon bar and select the screen.

The **Inter Branch Transaction Request** screen is displayed.

**Figure 8-8 Inter Branch Transaction Request**

The screenshot displays the 'Teller Transaction - Interbranch Transaction Request' interface. At the top, it shows the transaction ID 'TRN-0002308900340700' and the branch date 'Mar 30, 2018'. The main form is divided into several sections:
 

- Interbranch Transaction Request:** Contains 'New' and 'Query' buttons, and a text field for 'Inter Branch Request Reference'.
- Transaction Amount:** A dropdown menu set to 'GBP' and a text input field.
- Requesting Branch:** A text input field with '000' and a search icon.
- To Branch:** A text input field with a search icon.
- Request Type:** A dropdown menu.
- Cash Delivery/Pickup Date:** A date picker set to 'March 30, 2018'.
- Narrative:** A text area containing 'Inter Branch Transaction Request'.
- Transaction Amount (Required):** A dropdown menu set to 'GBP' and a text input field.
- Requesting Branch Description (Required):** A text input field with 'CITY HEAD OFFICE'.
- To Branch Description:** A text input field.
- Request Date:** A date picker set to 'March 30, 2018'.
- Request Status:** A dropdown menu set to 'Pending'.
- Denomination:** A section with a right-pointing arrow.


 On the right side, there is a 'Current Till Position' section with a gauge showing '£0.00' and a 'Memo Alerts' section with a 'No Data to Display' message. At the bottom right, there are 'Cancel', 'Submit', and 'Clear' buttons.

2. On the **Inter Branch Transaction Request** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 8-8 Inter Branch Transaction Request - Field Description**

Field	Description
<b>New</b>	Click this button to create a new inter branch transaction and generate the inter branch request reference number.
<b>Query</b>	Click <b>Query</b> to enable the field <b>Inter Branch Request Reference</b> .

Table 8-8 (Cont.) Inter Branch Transaction Request - Field Description

Field	Description
<b>Inter Branch Request Reference</b>	The following conditions apply to this field: <ul style="list-style-type: none"> <li>If you click <b>New</b>, the request reference number for the inter branch transaction is displayed.</li> <li>If you click <b>Query</b>, select the inter branch request reference from the list of values. The list of values fetches only the reference numbers that are saved and not submitted.</li> </ul>
<b>Transaction Amount</b>	Select the transaction currency from the option list. Specify the amount that needs to be transferred.
<b>Requesting Branch</b>	Displays the branch code of requesting branch.
<b>Requesting Branch Description</b>	Displays the name of the branch code specified.
<b>To Branch</b>	Select the branch code to which the request is being made.
<b>To Branch Description</b>	Displays the name of the specified <b>To Branch</b> .
<b>Request Type</b>	Select from the following request types: <ul style="list-style-type: none"> <li>Cash Delivery - when the branch is in short of cash.</li> <li>Cash Pickup - when the branch has excess cash.</li> </ul>
<b>Request Date</b>	Displays the current date as the request date.
<b>Cash Delivery/Pickup Date</b>	Specify the date of cash delivery/pickup. <div style="border: 1px solid #0070C0; padding: 5px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>By default, the current system date is displayed, and it can be modified.</p> </div>
<b>Request Status</b>	Select the status of the request. The drop-down list shows the following options: <ul style="list-style-type: none"> <li>Request - to create a new request.</li> <li>Accept - to accept a request received.</li> <li>Pending - system-defined status indicating that the request has been sent but not accepted.</li> <li>Initiated - system-defined status indicating that the request has been accepted and initiated.</li> <li>Liquidated - system-defined status indicating that the request has been processed and liquidated.</li> </ul>
<b>Narrative</b>	Specify the remarks, if any.

- Specify the denomination details. For information on the fields in the **Denomination** segment, refer to [Add Denomination Details](#).
- Click **Submit**.  
The request is sent to the receiving/remitting branch for further processing.

 **Note:**

The destination branch can access the same screen to accept or reject the request.

## 8.8.2 Inter Branch Transaction Input

The **Inter Branch Transaction Input** screen is used for a branch to act as a remitting branch to book an input transaction for cash delivery.


It is also used for the branch to act as a receiving branch to generate the advice and send it to the requesting branch. This option is allowed only after the destination branch has accepted the inter-branch transaction request.

To book an inter-branch transaction input:

1. On the **Home** screen, from **Teller** mega menu, under **Till-Vault Operations**, click **Inter Branch Txn Input** or specify **Inter Branch Txn Input** in the search icon bar and select the screen.


The **Inter Branch Transaction Input** screen is displayed.

**Figure 8-9 Inter Branch Transaction Input**



2. On the **Inter Branch Transaction Input** screen, specify the fields. For more information on fields, refer to the field description table.

Table 8-9 Inter Branch Transaction Input - Field Description

Field	Description
<b>Inter Branch Request Reference</b>	Select the request reference from the list of values.   <b>Note:</b>  Select the transaction reference number of the inter branch transaction request from the list of values.
<b>Query</b>	Click <b>Query</b> to fetch and populate the request details.
<b>From Branch</b>	Displays the branch code of <b>From Branch</b> . The following values are applied based on the request type in the <b>Inter Branch Transaction Request</b> screen: <ul style="list-style-type: none"> <li>For <b>Cash Delivery</b>, the <b>To Branch</b> in the <b>Inter Branch Transaction Request</b> screen is populated in this field.</li> <li>For <b>Cash Pickup</b>, the <b>Requesting Branch</b> in the <b>Inter Branch Transaction Request</b> screen is populated in this field.</li> </ul>
<b>From Branch Description</b>	Displays the description of the <b>From Branch</b> .
<b>From Vault ID</b>	Displays the Vault user of the specified <b>From Branch</b> .
<b>To Branch</b>	Displays the branch code of <b>To Branch</b> . The following values are applied based on the request type in the <b>Inter Branch Transaction Request</b> screen: <ul style="list-style-type: none"> <li>For <b>Cash Delivery</b>, the <b>Requesting Branch</b> in the <b>Inter Branch Transaction Request</b> screen is populated in this field.</li> <li>For <b>Cash Pickup</b>, the <b>To Branch</b> in <b>Inter Branch Transaction Request</b> screen is populated in this field.</li> </ul>
<b>To Branch Description</b>	Displays the description of specified <b>To Branch</b> .
<b>To Vault ID</b>	Displays the Vault user of <b>To Branch</b> .
<b>Transaction Amount</b>	Displays the transaction currency and transaction amount based on the request reference.
<b>Requested Date</b>	Displays the date on which the transaction is requested.
<b>Narrative</b>	Specify the remarks, if any.

- Specify the denomination details. For information on the fields in the **Denomination** segment, refer to [Add Denomination Details](#).
- Click **Submit**.

The request is sent to the requesting branch for further processing.

 **Note:**

The request status in the **Inter Branch Transaction Request** screen will be internally updated to *Initiated* for the related request reference number. In addition, the system will post the accounting entries (for example, Dr Sending Branch Inter Branch Transit GL & Cr Sending Branch Vault GL) for the Inter Branch Input transaction as per the settlement definition maintained for the function code, and advice will be generated on transaction completion.

## 8.8.3 Inter Branch Transaction Liquidation

The receiving branch can use the **Inter Branch Transaction Liquidation** screen to receive the cash by way of cash delivery or cash pickup, verify the advice with denomination units, and liquidate the request.

This screen can be accessed by:

- The requesting branch for cash delivery
- The receiving branch for cash pickup

To perform the inter-branch transaction liquidation:

1. On the **Home** screen, from **Teller** mega menu, under **Till-Vault Operations**, click **Inter Branch Txn Liq** or specify **Inter Branch Txn Liq** in the search icon bar and select the screen.

The **Inter Branch Transaction Liquidation** screen is displayed.

**Figure 8-10 Inter Branch Transaction Liquidation**

2. On the **Inter Branch Transaction Liquidation** screen, specify the fields. For more information on fields, refer to the field description table.

**Table 8-10 Inter Branch Transaction Liquidation - Field Description**

Field	Description
<b>Inter Branch Request Reference</b>	Select the request reference from the list of values.
<b>Query</b>	Click <b>Query</b> to fetch and populate the request details.
<b>From Branch</b>	Displays the branch code of <b>From Branch</b> .
<b>From Branch Description</b>	Displays the description of the <b>From Branch</b> .
<b>To Branch</b>	Displays the branch code of <b>To Branch</b> .
<b>To Branch Description</b>	Displays the description of specified To Branch.

**Table 8-10 (Cont.) Inter Branch Transaction Liquidation - Field Description**

Field	Description
<b>Transaction Amount</b>	Displays the transaction currency and transaction amount based on the request reference.
<b>Requested Date</b>	Displays the date on which the transaction is requested.
<b>Narrative</b>	Specify the remarks, if any.

3. Specify the denomination details. For information on the fields in the **Denomination** segment, refer to [Add Denomination Details](#).
4. Click **Submit**.

The system updates the request reference as **Liquidated** in the **Inter Branch Transaction Request** screen for the related request reference.

 **Note:**

The system will post the accounting entries (for example, Dr Receiving Branch Vault Transit GL & Cr Sending Branch Inter Branch Transit GL) for the Inter Branch Input transaction as per the settlement definition maintained for the function code.

As the liquidation transaction accounting involves two different branches, the corresponding IB position entries will be processed by FCUBS accordingly.



# A

## Functional Activity Codes

This topic provides the functional activity codes available in Oracle Banking Teller.

**Table A-1 List of Functional Activity Codes for Oracle Banking Teller**

Screen Name	Functional Activity Code	Action	Description
Cash Deposit	SRV_FA_CASH_DEPOSIT	NEW	Create a new Cash Deposit
Open Branch Batch	SRV_FA_OPEN_BRANCH_BATCH	NEW	Create a new Open Branch Batch
Open Vault Batch	SRV_FA_OPEN_VAULT_BATCH	NEW	Create a new Open Vault Batch
Open Teller Batch	SRV_FA_OPEN_TELLER_BATCH	NEW	Create a new Open Teller Batch
Close Teller Batch	SRV_FA_CLOSE_TELLER_BATCH	NEW	Create a new Close Teller Batch
Close Vault Batch	SRV_FA_CLOSE_VAULT_BATCH	NEW	Create a new Close Vault Batch
Close Branch Batch	SRV_FA_CLOSE_BRANCH_BATCH	NEW	Create a new Close Branch Batch
Branch Total Position	SRV_FA_TELLER_TOTALS_POSITION	NEW	Create a new Branch Total Position
Till Vault Position	SRV_FA_TILL_VAULT_POSITION	NEW	Create a new Till Vault Position
Current Open Tills	SRV_FA_CURRENT_OPEN_TILLS	QUERY	View Current Open Tills
Branch Breach Limits	SRV_FA_BRANCH_BREACHING_LIMITS	QUERY	View Branch Breach Limits
Electronic Journal	SRV_FA_ELECTRONIC_JOURNAL_LOG_CASH	QUERY	View Electronic Journal
Servicing Journal	SRV_FA_ELECTRONIC_JOURNAL_LOG_NON_CASH	QUERY	View Servicing Journal
Book Shortage	SRV_FA_BOOK_SHORTAGE	NEW	Create a new Book Shortage
Book Overage	SRV_FA_BOOK_OVERAGE	NEW	Create a new Book Overage
Buy Cash from Vault	SRV_FA_TRANSFERCASH_FROM_VAULT	NEW	Create a new Buy Cash from Vault
Sell Cash to Vault	SRV_FA_TRANSFERCASH_TO_VAULT	NEW	Create a new Sell Cash to Vault
Buy Cash from Till	SRV_FA_TRANSFERCASH_FROM_TILL	NEW	Create a new Buy Cash from Till
Sell Cash to Till	SRV_FA_TRANSFERCASH_TO_TILL	NEW	Create a new Sell Cash to Till
Buy Cash from Ccy Chest	SRV_FA_BUYCASH_FROM_CURRENCYCHEST	NEW	Create a new Buy Cash from Currency Chest

**Table A-1 (Cont.) List of Functional Activity Codes for Oracle Banking Teller**

Screen Name	Functional Activity Code	Action	Description
Sell Cash to Ccy Chest	SRV_FA_SELLCASH_TO_CURRENCYCHEST	NEW	Create a new Sell Cash to Currency Chest
Denomination Exchange	SRV_FA_DENOMINATION_EXCHANGE	NEW	Create a new Denomination Exchange
Misc GL Debit	SRV_FA_MISC_GL_DEBIT	NEW	Create a new Miscellaneous GL Debit
Misc GL Credit	SRV_FA_MISC_GL_CREDIT	NEW	Create a new Miscellaneous GL Credit
Misc GL Transfer	SRV_FA_GL_TRANSFER	NEW	Create a new Miscellaneous GL Transfer
Misc Customer Credit	SRV_FA_MISC_CUST_CREDIT	NEW	Create a new Miscellaneous Customer Credit
Misc Customer Debit	SRV_FA_MISC_CUST_DEBIT	NEW	Create a new Miscellaneous Customer Debit
Cash Withdrawal	SRV_FA_CASH_WITHDRAWAL	NEW	Create a new Cash Withdrawal
Cheque Withdrawal	SRV_FA_CASH_WITHDRAWAL	NEW	Create a new Cheque Withdrawal
Cheque Return	SRV_FA_CHEQUE_RETURN	NEW	Create a new Cheque Return
Account Transfer	SRV_FA_ACCOUNT_TRANSFER	NEW	Create a new Account Transfer
Account to Account Transfer	SRV_FA_ACC_TRF_DCT	NEW	Create a new Account to Account Transfer
In House Cheque Deposit	SRV_FA_INHOUSE_CHEQ_DEPOSIT	NEW	Create a new In House Cheque Deposit
Cheque Deposit	SRV_FA_CHEQUE_DEPOSIT	NEW	Create a new Cheque Deposit
In House Cheque Deposit	SRV_FA_INHOUSE_CHEQ_DEPOSIT_DIR	NEW	Create a new In House Cheque Deposit
Teller Branch Parameter Maintenance	SRV_FA_TELLER_GETALL_MENU	NEW	Create a new Teller Branch Parameter Maintenance
Branch Role Limits	SRV_FA_ROLELMT_GETALL_MENU	NEW	Create a new Branch Role Limits
Branch User Limits	SRV_FA_USER_PREF_GET_MENU	NEW	Create a new Branch User Limits
Denominations Maintenance	SRV_FA_DENOM_GETALL_MENU	NEW	Create a new Denominations Maintenance
Function Code Definition	SRV_FA_FUNC_CODE_DEFINITION_GET_MENU	NEW	Create a new Function Code Definition
Function Code Preferences	SRV_FA_BC_FUNC_PREF_GETALL_MENU	NEW	Create a new Function Code Preferences
Settlements Definition	SRV_FA_ACC_GETALL_MENU	NEW	Create a new Settlements Definition
Default Authorizer	SRV_FA_AUTHMAIN_GETALL_MENU	NEW	Create a new Default Authorizer
Inter Branch Transit Account	SRV_FA_IBTRANSITACCOUNT_GETALL_MENU	NEW	Create a new Inter Branch Transit Account

**Table A-1 (Cont.) List of Functional Activity Codes for Oracle Banking Teller**

Screen Name	Functional Activity Code	Action	Description
Channel Limits	SRV_FA_CHANNELMT_GETAL_MENU	NEW	Create a new Channel Limits
Charge Definition Maintenance	SRV_FA_CHARGEDEF_MAINT_GETAL_MENU	NEW	Create a new Charge Definition Maintenance
Create Charge Pricing Maintenance	SRV_FA_CREATE_PRCRULE_MENU	NEW	Create a new Create Charge Pricing Maintenance
View Charge Pricing Maintenance	SRV_FA_GET_PRCRULE_MENU	QUERY	View Charge Pricing Maintenance
Charge Condition Group Maintenance	SRV_FA_CHARGEGRP_GETAL_MENU	NEW	Create a new Charge Condition Group Maintenance
Charge Decision Maintenance	SRV_FA_CHARGE_PICK_GETAL_MENU	NEW	Create a new Charge Decision Maintenance
Branch Group Maintenance	SRV_FA_BRANCHGRP_GETAL_MENU	NEW	Create a new Branch Group Maintenance
Customer Group Maintenance	SRV_FA_CUSTGRP_GETAL_MENU	NEW	Create a new Customer Group Maintenance
Account Group Maintenance	SRV_FA_ACCGRP_GETAL_MENU	NEW	Create a new Account Group Maintenance
Reassign Transactions	SRV_FA_EJREASSIGN	NEW	Create a new Reassign Transactions
Denomination Variance Maintenance	SRV_FA_DENOMWISEVAR_GETAL_MENU	NEW	Create a new Denomination Variance Maintenance
External Bank Code	SRV_FA_BANKCOD_GETAL_MENU	NEW	Create a new External Bank Code
External System Maintenance	SRV_FA_EXTRNLSYS_GETAL_MENU	NEW	Create a new External System Maintenance
Miscellaneous Transfer	SRV_FA_MISC_TRANSFER	NEW	Create a new Miscellaneous Transfer
Reject Code Maintenance	REMO_FA_REJECTCODE_GETAL_MENU	NEW	Create a new Reject Code Maintenance
FX Purchase - Account	SRV_FA_FX_PURCHASE_AGAINST_ACC	NEW	Create a new FX Purchase against Account
FX Purchase - Walk-in	SRV_FA_FX_PURCHASE_WALKIN	NEW	Create a new FX Purchase against Walk-in
FX Purchase - Walk-in	SRV_FA_FX_PURCHASE_WALKIN_TELLER	NEW	Create a new FX Purchase against Walk-in
FX Sale - Account	SRV_FA_FX_SALE_AGAINST_ACC	NEW	Create a new FX Sale against Account
FX Sale - Walk-in	SRV_FA_FX_SALE_WALKIN	NEW	Create a new FX Sale against Walk-in
FX Sale - Walk-in	SRV_FA_FX_SALE_WALKIN_TELLER	NEW	Create a new FX Sale against Walk-in
Inter Branch Txn Input	SRV_FA_INTRBRANCH_SALE_VE_	NEW	Create a new Inter Branch Transaction Input

**Table A-1 (Cont.) List of Functional Activity Codes for Oracle Banking Teller**

Screen Name	Functional Activity Code	Action	Description
Inter Branch Txn Liq	SRV_FA_INTRBRANCH__LI Q_	NEW	Create a new Inter Branch Transaction Liquidation

# B

## Error Codes and Messages

The error codes and messages that are available for the Oracle Banking Branch application are provided in this appendix. The error codes with the prefix GCS apply only to the maintenance screens, and the remaining error codes apply to all the transaction screens.

**Table B-1 Error Codes and Messages**

Error Code	Message
CLMO-AC-003	Source stage value should be either Y/N not valid
CLMO-AC-017	DatasegmentCode not valid
CLMO-AC-018	DocumentType Code not valid
CLMO-AC-020	Life cycle not valid
CLMO-AC-023	Unable to \$1 Business Process as \$2 data segment has the following dependencies \$3 in lifecycle \$4
CLMO-AC-024	Unable to \$1 Business Process as the mandatory data segments \$2 for the \$3 lifecycle have not been mapped!
CLMO-AC-026	In \$1 stage of \$2 Business Process
CLMO-AC-027	Record already exist with same Lifecycle and Business Product
CLMO-AC-028	At \$1 in \$2 stage of \$3 Business Process
CLMO-AC-029	At \$1 in \$2 stage of \$3 Business Process
CLMO-AC-030	Business Product Code is Invalid
GCS-AUTH-01	Record Successfully Authorized
GCS-AUTH-02	Valid modifications for approval were not sent. Failed to match
GCS-AUTH-03	Maker cannot authorize
GCS-AUTH-04	No valid unauthorized modifications found for approval.
GCS-CLOS-002	Record Successfully Closed
GCS-CLOS-01	Record Already Closed
GCS-CLOS-02	Record Successfully Closed
GCS-CLOS-03	Unauthorized record cannot be closed
GCS-COM-001	Record does not exist
GCS-COM-002	Invalid version sent
GCS-COM-003	Please Send Proper ModNo

**Table B-1 (Cont.) Error Codes and Messages**

<b>Error Code</b>	<b>Message</b>
GCS-COM-004	Please send makerId in the request
GCS-COM-005	Request is Null. Please Resend with Proper Values
GCS-COM-006	Unable to parse JSON
GCS-COM-007	Request Successfully Processed
GCS-COM-008	Modifications should be consecutive.
GCS-COM-009	Resource ID cannot be blank or "null".
GCS-COM-010	You have successfully cancelled \$1.
GCS-COM-011	Argghhh, \$1 failed to update.
GCS-DEL-001	Record deleted successfully
GCS-DEL-002	Record(s) deleted successfully
GCS-DEL-003	Modifications didnt match valid unauthorized modifications that can be deleted for this record
GCS-DEL-004	Send all unauthorized modifications to be deleted for record that is not authorized even once.
GCS-DEL-005	Only Maker of first version of record can delete modifications of record that is not once authorized.
GCS-DEL-006	No valid unauthorized modifications found for deleting
GCS-DEL-007	Failed to delete. Only maker of the modification(s) can delete.
GCS-MOD-001	Closed Record cannot be modified
GCS-MOD-002	Record Successfully Modified
GCS-MOD-003	Record marked for close
GCS-MOD-004	Only maker of the record can modify before once auth
GCS-MOD-005	Not amendable field
GCS-MOD-006	Natural Key cannot be modified
GCS-MOD-007	Psssttt, only the maker can modify the pending records.
GCS-OPEN-01	Teller Batch Record Already Opened
GCS-REOP-003	Successfully Reopened
GCS-REOP-004	Unauthorized record cannot be reopened
GCS-REOP-01	Unauthorized Record cannot be Reopened
GCS-REOP-02	Failed to Reopen the Record

**Table B-1 (Cont.) Error Codes and Messages**

<b>Error Code</b>	<b>Message</b>
GCS-REOP-03	Successfully Reopened
GCS-SAV-001	Record already exists
GCS-SAV-002	Record Saved Successfully.
GCS-SAV-003	Congratulations!! The record is saved and validated successfully.
GCS-SAV-004	Currency Code should be unique
GCS-SAV-005	Min cash holding should be lesser than Max cash holding
GCS-VAL-001	Congratulations!! Your record is successfully validated.
RM_BC_CV_01	Amount Limit Exceeded for Account Number
RM_BC_CV_02	Amount Limit Exceeded for Customer Type
RM_BC_CV_03	Amount Limit Exceeded for Product Class
RM_BC_MA_01	Netting Charges Required Should be (Y/N).
RM_BC_MA_02	Main Leg Accounting Required Should be (Y/N).
RM_BC_MN_01	Invalid function code for till/vault indicator
RM_BC_MN_02	Invalid transaction type for till/vault indicator
RM_BC_OB_08	Please close the previous day batch
RM_BC_OB_09	User is not allowed to open the Teller batch
RM_BC_OB_10	Teller batches should be closed before closing the branch/vault batch
RM_BC_OB_11	Vault batch should be closed before closing the branch batch
RM_BC_TB_10	Teller batch is already opened
RM_BC_TB_11	Teller batch is already closed
RM_BC_VA_01	Supervisor Id is not present for manual assignment.
RM_CS_BC_01	Invalid Instrument No
RM_CS_BC_02	Instrument is already in Used status
RM_CS_BC_03	Instrument is not in INIT status to Print/ Reprint
RM_CS_BC_04	Instrument Number Already Liquidate
RM_CS_DD_04	Incorrect DD details
RM_CT_AC_03	Account Type mismatch.... Exception Occured
RM_CT_AC_04	Invalid Account Number
RM_CT_AC_06	Both Account cannot be Customer Accounts

**Table B-1 (Cont.) Error Codes and Messages**

<b>Error Code</b>	<b>Message</b>
RM-IN-TX-01	Payments Service is not Reachable
RM_TR_EX_01	Unhandled Exception Occured
RM_TX_CX_01	Authorization required for Charge Amendment.
RM_TX_EX_01	Authorization required for inter branch Transaction.
RM-AD-EC-01	Failed in ECA
RM-AD-HH-01	Failed in Host Handoff
RM-AD-PM-03	Failed in payment
RM-AD-UB-01	Failed in DDA system
RM-AD-VM-01	Invalid Account Number
RM-AD-VM-02	VAM Service is down
RM-BC-AC-01	Failed in Accounting
RM-BC-BP-01	Please Enter the entire Branch Parameter Detail values
RM-BC-CH-01	Minimum Charge Greeater Than Maximum Charge
RM-BC-CH-02	Please Enter the proper charge code
RM-BC-CH-03	Charge Fields Cannot be empty
RM-BC-CH-04	Please Enter Mininum and Maximum Charges
RM-BC-CP-03	Function code should not be empty
RM-BC-EJ-01	Record Not Found
RM-BC-EJ-02	Record Updation Failed..
RM-BC-EX-01	Unhandled Exception Occured
RM-BC-EX-02	Transaction Timed Out
RM-BC-EX-03	Unhandled Exception Occured
RM-BC-ML-01	Email Account not Valid
RM-BC-OB-01	Branch batch is already open for the current date
RM-BC-OB-02	Branch batch can be opened only by supervisor
RM-BC-OB-03	Vault batch is open for the current or previous date
RM-BC-OB-04	User does not have rights to access this screen
RM-BC-OB-05	Teller batch is open for the current or previous date
RM-BC-OB-06	Please complete the pending transactions in the Electronic Journal log
RM-BC-OB-07	Branch batch is not opened
RM-BC-OB-08	Please close the previous day batch



**Table B-1 (Cont.) Error Codes and Messages**

<b>Error Code</b>	<b>Message</b>
RM-BC-OB-10	Teller batches should be closed before closing the branch/vault batch
RM-BC-OB-11	Vault batch should be closed before closing the branch batch
RM-BC-OB-16	Teller batch is closed
RM-BC-OB-17	Teller batch is not opened for the user
RM-BC-OB-18	Teller batch is already open
RM-BC-OB-19	Teller batch is closed
RM-BC-OB-20	Invalid Currency Code
RM-BC-OB-21	Authlimit Breached
RM-BC-OB-22	Transaction limit breached at role level
RM-BC-OB-23	Wrong token
RM-BC-OB-24	Branch batch is already closed
RM-BC-OB-25	Vault batch is already closed
RM-BC-OB-26	User is not allowed to open/close the teller batch
RM-BC-OB-27	Vault batch is not opened
RM-BC-OB-29	Please maintain denomination tracking in Branch Parameter
RM-BC-OB-30	Denomination Amount is not equal to transaction amount
RM-BC-OB-31	Insufficient Amount available in Till/Vault
RM-BC-OB-32	Logged in user ID and Teller Id cannot be same
RM-BC-OB-33	Invalid Input TellerId
RM-BC-OB-34	Current Denomination balance is less than zero for \$1
RM-BC-PM-01	Record Successfully Updated
RM-BC-RT-01	Failed in getting the exchange rate
RM-BC-RT-02	Failed to fetch Branch Accounting Tags
RM-BC-TF-01	User not Verified Signature
RM-BC-TF-02	Transaction involves Inter Bank Accounts
RM-BC-TF-03	Default Charge Amount was modified
RM-BC-TF-04	Default Exchange Rate was modified
RM-BC-TF-05	Amount exceeds limit for this transaction
RM-BC-TF-06	Authorisation required. Amount exceeds limit for the transaction

**Table B-1 (Cont.) Error Codes and Messages**

<b>Error Code</b>	<b>Message</b>
RM-BC-TF-07	Transaction & Electronic Journal ID needs to be Enter..
RM-BC-TF-08	Invalid Txn_Ref_Number found for given EJId
RM-BC-TR-07	Invalid Input!!
RM-BC-UL-01	User Limit Transaction Amount breached
RM-BC-UL-02	Authorizer Limit Transaction Amount breached
RM-BC-UL-03	User Limit Holding Minimum Amount breached
RM-BC-UL-04	User Limit Holding Maximum Amount breached
RM-BC-UP-01	Amount exceeds limit for this transaction
RM-BC-UP-02	Minimum charge amount should be applied
RM-BC-UP-03	Amount exceeds limit for this transaction
RM-BC-UP-04	Authorisation amount breached.
RM-BC-UP-05	Till maximum balance breached
RM-BC-UP-06	Till minimum balance breached
RM-BC-UP-07	Authoriser role limit breached
RM-BC-UP-08	Teller role limit breached
RM-BC-UP-09	Transaction requires approval.
RM-BC-UR-01	Submit URL not maintained
RM-BC-VA-01	Till open
RM-BC-VA-02	Vault1 open
RM-BC-VA-03	Pending txn
RM-BC-VA-10	Invalid Status
RM-BC-XR-01	Exchange not Maintained
RM-BC-XT-01	Failed in getting the exchange rate
RM-CH-LM-01	Channel limit not found for Account class group
RM-CH-LM-02	Channel limit details not found
RM-CH-LM-03	Channel limit details found for transaction currency
RM-CH-LM-04	Number of Withdrawal breached
RM-CH-LM-05	Withdrawal Limit breached
RM-CM-OR-001	Failed to initiate.
RM-CM-OR-002	Transaction is successfully initiated.
RM-CM-OR-003	Invalid action
RM-CM-OR-004	\$1 is not submitted
RM-CM-OR-005	Cannot proceed with submit as the action is not initiated.

**Table B-1 (Cont.) Error Codes and Messages**

<b>Error Code</b>	<b>Message</b>
RM-CM-OR-006	Cannot proceed with submit as the information is incomplete.
RM-CM-OR-007	Failed to submit.
RM-CM-OR-008	Record successfully submitted.
RM-CM-OR-009	\$1 is in-progress
RM-CM-OR-010	Aw, snap! An unexpected exception occurred, try again.
RM-CM-OR-011	Invalid request.
RM-CM-OR-012	Cannot proceed with submit as the action is not initiated.
RM-CM-OR-013	Cannot find the provided information.
RM-CM-OR-014	Record is not yet submitted by \$1
RM-CM-OR-015	Record already unlocked by \$1.
RM-CS-OB-01	Invalid denomination found
RM-CS-OB-02	Invalid denomination found for given currency or denomination type
RM-CS-OB-03	Transaction Number Already Exist
RM-CS-OB-04	Data Not Found
RM-CS-OB-05	Amount mismatch
RM-CS-OB-50	SanctionRefNo is already Present.
RM-CS-TF-07	MinCash exceeds the MaxCash Value
RM-CT-AC-01	Charges are not maintained
RM-CT-AC-02	Charges should not be maintained
RM-CT-AC-04	Failed to get the account
RM-EX-CS-01	User is an Invalid User.
RM-EX-CS-02	Account number is invalid.
RM-EX-CS-03	Source Reference Number Already Present
RM-EX-CS-05	NegotiatedExchangeRate is not provided
RM-EX-CS-06	NegotiationReferenceNumber is not provided
RM-EX-PY-05	NegotiatedExchangeRate is not provided
RM-EX-PY-06	NegotiationReferenceNumber is not provided
RM-PA-EQ-01	Record not Found.
RM-PY-AC-01	From account and to account are same
RM-PY-AC-02	Account number not entered for field \$1
RM-PY-BC-01	Bank code or bank BIC code not entered
RM-PY-BC-02	Please enter either bank code or bank BIC code

**Table B-1 (Cont.) Error Codes and Messages**

<b>Error Code</b>	<b>Message</b>
RM-PY-CL-01	Payee account and drawer account are same
RM-PY-CL-02	Drawer account number and instrument number combination are same
RM-PY-CL-03	Invalid Batch Number
RM-PY-CR-01	Remittance number not found
RM-PY-CR-02	Remittance number is already issued/used
RM-PY-CR-03	Please provide Remittance number/Test Key number
RM-PY-CR-04	Invalid Remittance number/Test Key number
RM-PY-CR-05	Remittance numbers are not maintained
RM-PY-CR-06	Maintained remittance numbers are all USED ones
RM-PY-IN-01	Instrument details not found
RM-TD-SL-01	No Maintenance found for Term Deposit opening
RM-TD-SL-02	Offset GL account not found
RM-TN-RV-02	The transaction Status should be pending
RM-TR-EX-01	Unhandled Exception Occured
RM-TS-TB-10	Teller batch not opened yet
RM-TX-BE-01	Unhandled Exception Occured
RM-TX-CA-01	Charge amount limit Breached from Min Max Amount
RM-TX-CA-02	Charge amount limit Breached from Min Max Percentage
RM-TX-CC-01	Add provided Currency to the Till
RM-TX-ET-01	Session should be Opened before closing.
RM-TX-ET-02	Amount \$1 \$2 has to be given by the customer.
RM-TX-ET-03	Amount \$1 \$2 has to be given to the customer.
RM-TX-ET-04	The incoming cash amount in the session is exceeding by \$1 \$2.Do you want to proceed.
RM-TX-ET-05	Open Teller Sessions are present. Cannot proceed with the operation.
RM-TX-ET-06	Teller Session Transactions not completed.Cannot proceed with the operation.
RM-TX-EX-01	Unhandled Exception Occured
RM-TX-HH-01	Failed in Host Handoff
RM-TX-LC-01	Transaction is locked
RM-TX-LI-00	Amount exceeds the limit of transaction.
RM-TX-NL-01	Unhandled Exception Occured

**Table B-1 (Cont.) Error Codes and Messages**

<b>Error Code</b>	<b>Message</b>
RM-TX-OC-01	Branch Info not available
RM-TX-OC-02	Function Code definition not maintained
RM-TX-OC-03	Function Code preferences not maintained
RM-TX-OC-04	Branch Parameter maintenance not found
RM-TX-OC-05	User preferences not maintained
RM-TX-OC-06	Default authorizer not maintained for the user
RM-TX-OC-07	Function Indicator entry not found
RM-TX-OC-08	Record status is null in Function Code Definition Screen
RM-TX-OC-09	Record status is closed in Function Code Definition Screen
RM-TX-OC-10	Record status is null in User Preferences Screen
RM-TX-OC-11	Record status is closed in User Preferences Screen
RM-TX-OC-12	Record status is null in Function Code Preferences Screen
RM-TX-OC-13	Record status is closed in Function Code Preferences Screen
RM-TX-PM-01	Transaction status is pending, waiting for the notification from payment system
RM-TX-PM-03	Failed in payment system
RM-TX-RV-01	The transaction Status should be completed
RM-TX-RV-02	Only maker can reverse the transaction
RM-TX-RV-03	Authorization required for reversal
RM-TX-RV-04	Minimum teller branch ccy holding limit breached
RM-TX-RV-05	Maximum teller branch ccy holding limit breached
RM-TX-SL-01	Unhandled Exception Occured
RM-TX-ST-01	The incoming cash amount in the session is exceeding by \$1.Do you want to proceed.
RM-TX-ST-02	Total inflow cash amount remaining after this transaction is \$1.
RM-TX-ST-03	Another open session in progress for the entered Customer No
RM-TX-ST-04	Another open session in progress for the Teller
RM-TX-ST-05	Teller session needs to be opened to perform this transaction.

**Table B-1 (Cont.) Error Codes and Messages**

<b>Error Code</b>	<b>Message</b>
RM-TX-ST-06	This transaction is not allowed inside the teller session
RM-TX-TO-01	Unhandled Exception Occured
RPM-AC-003	Source stage value should be either Y/N not valid
RPM-AC-017	DatasegmentCode not valid
RPM-AC-018	DocumentType Code not valid
RPM-AC-020	Life cycle not valid
RPM-AC-023	Unable to \$1 Business Process as \$2 data segment has the following dependencies \$3 in lifecycle \$4
RPM-AC-024	Unable to \$1 Business Process as the mandatory data segments \$2 for the \$3 lifecycle have not been mapped!
RPM-AC-026	In \$1 stage of \$2 Business Process
RPM-AC-027	Record already exist with same Lifecycle and Business Product
RPM-AC-028	At \$1 in \$2 stage of \$3 Business Process
RPM-AC-029	At \$1 in \$2 stage of \$3 Business Process
RPM-AC-030	Business Product Code is Invalid
RT-F23-001	Error. Enter at least one row in Payment Data Details
RT-F23-002	Error. Cannot enter more than eight records in Payment Data Details
RT-F23-006	Error. Mandatory Field Payment Type Cannot be Null.
RT-F23-007	Error. Fiscal Code has to be 11 or 16 character long.
RT-F23-008	Error. Fiscal code does not meet checksum algorithm validations
RT-F23-017	Error. Enter at least one field in either Reference Number Available or Reference Number Not Available.
RT-F23-019	Error. Both Reference Number and Primary fiscal code cannot be null.
RT-F23-020	Invalid character entered for Tax Code
RT-F24-099	Payment Amount Cannot be Zero/Negative
RT-F24-101	Payment amount should not Be Blank
RT-F24-114	Principal fiscal code is mandatory

# C

## List of Function Codes

The list of function codes and their respective names for all the transaction screens of the Oracle Banking Branch application are provided in this appendix.

**Table C-1 List of Function Codes**

Function Code	Screen Name
0006	Account to Account Transfer
0007	In-House Check Deposit
1000	Miscellaneous Transfer
1001	Cash Withdrawal
1005	Miscellaneous GL Transfer
1008	Miscellaneous Customer Debit
1013	Check Withdrawal
1060	Miscellaneous GL Debit
1401	Cash Deposit
1408	Miscellaneous Customer Credit
1460	Miscellaneous GL Credit
6001	Open Branch Batch
6002	Close Branch Batch
6005	Electronic Journal
7001	Open Vault Batch
7002	Close Vault Batch
7005	Servicing Journal
7040	Branch Total Position
7551	Book Shortage
7552	Book Overage
9001	Open Teller Batch
9002	Close Teller Batch
9005	Buy Cash from Till
9006	Sell Cash to Till
9007	Buy Cash from Vault
9008	Sell Cash to Vault
9009	Buy Cash from Currency Chest
9010	Sell Cash to Currency Chest
9012	Current Open Tills
DNEX	Denomination Exchange

**Table C-1 (Cont.) List of Function Codes**

<b>Function Code</b>	<b>Screen Name</b>
REAN	Reassign Transactions
TVQB	Branch Breaching Limits
TVQR	Till Vault Position



# D

## Order of Replacing Parameters with Wild Card Entries

The order of replacing parameters with wild card entries is required for the Accounting and Settlements Definition and Charge Decision Maintenance.

**Table D-1 Order for Accounting and Settlements Definition**

Function Code	Branch	Currency
Function Code	Txn Branch	Txn Currency
Function Code	*.*	Txn Currency
Function Code	Txn Branch	*.*
Function Code	*.*	*.*

**Table D-2 Order for Charge Pickup**

Function Code	Txn Branch	Txn Currency	Inter Branch
Function Code	Txn Branch	Txn Currency	Y
Function Code	Txn Branch	Txn Currency	N
Function Code	*.*	Txn Currency	Y
Function Code	*.*	Txn Currency	N
Function Code	Txn Branch	*.*	Y
Function Code	Txn Branch	*.*	N

**Table D-3 Order for Charge Group**

Parameter1	Parameter2	Parameter3	Parameter4	Parameter5
Parameter1	Parameter2	Parameter3	Parameter4	Parameter5
Parameter1	Parameter2	Parameter3	Parameter4	*.*
Parameter1	Parameter2	Parameter3	*.*	Parameter5
Parameter1	Parameter2	*.*	Parameter4	Parameter5
Parameter1	*.*	Parameter3	Parameter4	Parameter5
*.*	Parameter2	Parameter3	Parameter4	Parameter5
*.*	*.*	Parameter3	Parameter4	Parameter5
Parameter1	*.*	*.*	Parameter4	Parameter5
Parameter1	Parameter2	*.*	*.*	Parameter5
Parameter1	Parameter2	Parameter3	*.*	*.*
Parameter1	Parameter2	*.*	*.*	*.*

Table D-3 (Cont.) Order for Charge Group

Parameter1	Parameter2	Parameter3	Parameter4	Parameter5
Parameter1	*. *	*. *	*. *	Parameter5
*. *	*. *	*. *	Parameter4	Parameter5
*. *	*. *	*. *	*. *	Parameter5
Parameter1	*. *	*. *	*. *	*. *
*. *	*. *	*. *	*. *	*. *

# E

## Static Maintenance Parameters

The descriptions for the column names of the significant parameters in the static maintenance tables are provided in this appendix. If required, the user needs to modify these parameters in the respective static maintenance tables.

**Table E-1 Columns in SRV\_TM\_BC\_FUNCTION\_INDICATOR Table**



Column Name	Description
<i>CROSS_CCY_ENABLED</i>	<p>This column indicates whether the cross-currency is allowed for a transaction or not. The user can modify this flag to enable/disable the cross-currency configuration. Possible values are as follows:</p> <ul style="list-style-type: none"> <li>• <b>Y</b> – Yes</li> <li>• <b>N</b> – No</li> </ul> <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>When the value is set to <b>N</b>, the <b>Exchange Rate</b> fields will be hidden.</p> </div>
<i>DENOM_VARIANCE</i>	<p>This column indicates the applicability of denomination variance. The user can modify this flag to enable/disable the denomination variance. Possible values are as follows:</p> <ul style="list-style-type: none"> <li>• <b>Y</b> – Yes</li> <li>• <b>N</b> – No</li> </ul> <div style="border-left: 2px solid #0070C0; padding-left: 10px; margin-top: 10px;"> <p> <b>Note:</b></p> <p>This flag applies only to the function codes – 8004, 8203, 8206, and 8207.</p> </div>
<i>IS_NEGOTIATED_RATE_ENABLED</i>	<p>This column indicates whether the <b>Negotiated Exchange Rate</b> field is required on the screen or not. The user can modify this flag to enable/disable the <b>Negotiated Exchange Rate</b> for a specified screen. Possible values are as follows:</p> <ul style="list-style-type: none"> <li>• <b>Y</b> – Yes</li> <li>• <b>N</b> – No</li> </ul>
<i>IS_REVERSAL_SUPP</i>	<p>This column indicates whether the transaction reversal is supported or not. The user can modify this flag to enable/disable the reversal for a particular transaction. Possible values are as follows:</p> <ul style="list-style-type: none"> <li>• <b>Y</b> – Yes</li> <li>• <b>N</b> – No</li> </ul>

Table E-1 (Cont.) Columns in SRV\_TM\_BC\_FUNCTION\_INDICATOR Table

Column Name	Description
<i>IS_TELLER_SEQ_REQ</i>	This column indicates whether the Teller Sequence Number generation is required or not. The user can modify this flag to enable/disable the Teller Sequence Number generation for a particular transaction. Possible values are as follows: <ul style="list-style-type: none"> <li>• <b>Y</b> – Yes</li> <li>• <b>N</b> – No</li> </ul>
<i>IS_TOT_CHARGES_REQ</i>	This column indicates whether the <b>Total Charges</b> field is required on the screen or not. The user can modify this flag to enable/disable the <b>Total Charges</b> for a particular transaction. Possible values are as follows: <ul style="list-style-type: none"> <li>• <b>Y</b> – Yes</li> <li>• <b>N</b> – No</li> </ul>

Table E-2 Columns in SRV\_TB\_BC\_ARCHIVAL Table

Column Name	Description
<i>ARCHIVAL_DAYS</i>	This column indicates the number of days required for the archival. The user can modify this flag to update the number of days.
<i>BRANCH_CODE</i>	This column indicates the Branch Code, based on which the lookup of Archival details will happen. It refers to the branch in which the archival will happen. The user can modify this flag to update the Branch Code.

# Glossary

# Index

## A

---

Account Group Maintenance, [7-33](#)  
Account Transfer, [3-1](#)

## B

---

Book Overage, [2-21](#)  
Book Shortage, [2-18](#)  
Branch Breach Limits, [2-8](#)  
Branch Group Maintenance, [7-45](#)  
Branch Role Limits, [7-15](#)  
Branch Total Position, [2-11](#)  
Branch User Limits, [7-7](#)  
Buy Cash from Currency Chest, [8-4](#)  
Buy Cash from Till, [8-3](#)  
Buy Cash from Vault, [8-1](#)

## C

---

Cash Deposit, [5-1](#)  
Cash Withdrawal, [5-6](#)  
Channel Limits Maintenance, [7-9](#)  
Charge Condition Group Maintenance, [7-39](#)  
Charge Decision Maintenance, [7-38](#)  
Charge Definition Maintenance, [7-19](#)  
Check Withdrawal, [5-9](#)  
Close Branch Batch, [2-17](#)  
Close Teller Batch, [2-12](#)  
Close Vault Batch, [2-15](#)  
Create Charge Pricing Maintenance, [7-17](#)  
Current Open Tills, [2-7](#)  
Customer Group Maintenance, [7-42](#)

## D

---

Default Authorizer Maintenance, [7-44](#)  
Denomination Exchange, [8-8](#)  
Denomination Variance Maintenance, [7-21](#)  
Denominations Maintenance, [7-2](#)

## E

---

Electronic Journal, [4-4](#)

External Bank Code, [7-36](#)  
External System Maintenance, [7-34](#)

## F

---

Function Code Definition, [7-11](#)  
Function Code Preferences, [7-23](#)  
Functional Activity Codes, [A-1](#)  
FX Purchase Against Account, [5-19](#)  
FX Purchase Against Walk-in, [5-22](#)  
FX Sale Against Account, [5-12](#)  
FX Sale Against Walk-in, [5-16](#)

## I

---

In-House Check Deposit, [3-3](#)  
Inter Branch Transaction Input, [8-14](#)  
Inter Branch Transaction Liquidation, [8-16](#)  
Inter Branch Transaction Request, [8-12](#)  
Inter Branch Transit Account Maintenance, [7-4](#)

## M

---

Miscellaneous Customer Credit, [6-4](#)  
Miscellaneous Customer Debit, [6-1](#)  
Miscellaneous GL Credit, [6-9](#)  
Miscellaneous GL Debit, [6-7](#)  
Miscellaneous GL Transfer, [6-12](#)  
Miscellaneous Transfer, [6-14](#)

## O

---

Open Branch Batch, [2-2](#)  
Open Teller Batch, [2-5](#)  
Open Vault Batch, [2-3](#)

## R

---

Reassign Transactions, [4-11](#)  
Reject Code Maintenance, [7-31](#)

## S

---

Sell Cash to Currency Chest, [8-6](#)

Sell Cash to Till, [8-7](#)  
Sell Cash to Vault, [8-9](#)  
Servicing Journal, [4-7](#)  
Settlements Definition, [7-28](#)  
Static Data, [7-47](#)

## T

---

Teller Branch Parameters Maintenance, [7-6](#)

Till Vault Position, [2-10](#)

## V

---

View Charge Pricing Maintenance, [7-18](#)