

Oracle Life Sciences Warehouse

API Guide



Release 3.4.1

G15207-01

September 2024

ORACLE®

Copyright © 2017, 2024, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Contents

Preface

Documentation accessibility	xviii
Related resources	xviii
Diversity and Inclusion	xviii
Access to Oracle Support	xviii

Part I Essential Information

1 Using Application Programming Interfaces

About APIs	1-1
Example 1: Using APIs to Perform Multiple Tasks at Once	1-1
Example 2: Calling APIs from an External System's UI	1-2
Understand Oracle LSH Functionality	1-2
Tips	1-3
Committing APIs	1-3
Get Attribute Values for Namespace Objects	1-3
Calling APIs from Outside Oracle LSH	1-3
Security Setup Required	1-3
Calling the Security API Package	1-4
Calling APIs from SAS	1-4
Using a Permanent Schema for Deploying Programs that Call APIs	1-5
Calling APIs from Defined Programs	1-5
Code Example Using Security and Error Message APIs	1-6

2 Reference Information

CDR Naming Version Object Type	2-1
CDR Base Object Type	2-3
CDR Object-Specific Database Object Types	2-3
Retrieving Reference Codelist Names and Values	2-4
Retrieving the Instance Domain ID	2-5
Retrieving the ID of a User-Defined Domain	2-5

CDR_DF_NAMING_V View	2-5
Standard Parameters	2-5

3 Access to Private Oracle DMW and Oracle LSH Tables

Part II Object APIs

4 Application Areas

Define and Modify Application Areas	4-1
Create an Application Area	4-1
Modify an Application Area	4-2
Remove an Application Area	4-2
Copy Objects into an Application Area	4-3
Move Objects into an Application Area	4-4

5 Business Areas

Define and Modify Business Areas	5-1
Create a Business Area	5-1
Modify a Business Area	5-3
Check Out a Business Area	5-3
Undo a Business Area Checkout	5-4
Check In a Business Area	5-4
Remove a Business Area	5-5
Create and Modify Business Area Hierarchies	5-6
Create a Business Area Hierarchy	5-6
Modify a Hierarchy and a Hierarchy Column	5-7
Reorder a Hierarchy Column	5-7
Remove a Hierarchy Column	5-8
Remove a Business Area Hierarchy	5-9
Create and Modify Business Area Joins	5-9
Create a Join	5-9
Modify a Join and a Join Column	5-10
Remove a Join Column	5-11
Remove a Join	5-12
Public APIs and Naming Views for Generic Visualization Adapter (GVA)	5-12
Initialize a Generic Visualization Business Area Instance	5-13
Reset a Generic Visualization Business Area Instance	5-14
Get Possible Blinding Types of a Business Area Instance	5-15

Get Snapshot Labels Common to all Tables in a BA Instance for a Given Blinding AccessType	5-15
Get Custom Listing Business Area ID	5-16
Initialize Only Discrepancy View for Oracle DMW Business Area	5-16

6 Data Marts

Define and Modify Data Marts	6-1
Create a Data Mart	6-1
Check In a DataMart Definition	6-2
Modify a Data Mart	6-3
Check Out a Data Mart	6-4
Remove a Data Mart	6-4

7 Domains

Define and Modify Domains	7-1
Create a Domain	7-1
Modify a Domain	7-2
Copy a Domain	7-2
Move Objects into a Domain	7-3
Copy Objects into a Domain	7-4
Check in Objects and Copy them into a Different Domain	7-4
Remove a Domain	7-5

8 Load Sets

Define and Modify Load Sets	8-1
Create a Load Set	8-1
Check Out a Load Set	8-2
Modify a Load Set	8-3
Check In a Load Set Definition	8-4
Undo Check Out for a Load Set Definition	8-5
Remove a Load Set	8-5
Synchronize Table Descriptors in a Load Set	8-6

9 Parameter Sets

Create and Modify Parameter Sets	9-1
Create a Parameter Set Definition	9-1
Check Out a Parameter Set Definition	9-2
Modify a Parameter Set Definition	9-3
Modify a Parameter Set Detail	9-4

Check In a Parameter Set Definition	9-4
Remove a Parameter Set Definition	9-5

10 Planned Outputs

Create and Modify Planned Outputs	10-1
Create a Planned Output	10-1
Get a New Position Number	10-2
Get a Planned Output Object	10-3
Modify a Planned Output	10-3
Identify whether a SAS Object	10-4
Remove a Planned Output Object	10-5

11 Programs

Create and Modify Programs	11-1
Create a Program	11-1
Copy Objects Into a Program	11-3
Modify a Program	11-3
Check In a Program Definition	11-4
Check Out a Program Definition	11-5
Remove a Program	11-5
Create a Planned Output for a Log File	11-6
Assign a Planned Output	11-7
Modify a Manual Validation Flag Value	11-7

12 Software Source Codes

Create and Modify Source Code	12-1
Create a Source Code Object	12-1
Get a Source Code CLOB	12-2
Modify Source Code	12-3
Set the Primary Flag to Yes	12-5
Update a Shareable Flag	12-5
Remove a Source Code Object	12-6

13 Tables

Create and Modify Tables	13-1
Create a Table Definition	13-1
Create a Table Instance	13-2
Create a Temporary Blob	13-4

Create a Table Column	13-4
Modify a Table Column	13-5
Create a Table Constraint	13-6
Modify a Table Constraint	13-7
Modify a Table Definition	13-7
Create a Table Descriptor	13-8
Modify a Table Descriptor	13-9
Modify a Table Instance	13-10
Reorder a Column	13-11
Upload a Table Descriptor or Column	13-11
Check Out a Table	13-12
Check In a Table	13-13
Undo Check Out for a Table Definition	13-13
Remove a Single Object	13-14

14 Parameters

Define and Modify Parameters	14-1
Create a Parameter	14-1
Check Out a Parameter	14-3
Check In a Parameter	14-3
Get Displayed Parameter Values	14-4
Define Parameter Relations	14-5
Create a Parameter Relation Collection	14-5
Get Parameter Instances for Value Passing	14-6
Remove Parameter Relations	14-6

15 Variables

Create and Modify Variables	15-1
Create a Variable	15-1
Check Out a Variable	15-2
Modify a Variable	15-3
Check In a Variable	15-3
Remove a Variable	15-4

16 Work Areas

Define and Modify Work Areas	16-1
Create a Work Area	16-1
Install a Work Area	16-2
Check In a Work Area	16-3

Modify a Work Area	16-4
Clone a Work Area	16-4
Copy Objects into a Work Area	16-5
Clone an Object	16-6
Remove a Work Area	16-7
Get the Usage Intent RC of a Work Area	16-7
Update a Work Area's Usage Intent	16-8
Install a Program	16-8
Apply or Move a Snapshot Label	16-9
Remove a Snapshot Label from a Work Area	16-11

17 Workflows

Create and Modify Workflows	17-1
Create a Workflow	17-1
Check Out a Workflow Definition	17-2
Create a Workflow Transition	17-3
Create a Workflow Structure Instance	17-4
Modify a Workflow	17-4
Modify a Workflow	17-5
Check In a Workflow Definition	17-5
Remove a Transition	17-6
Remove a Workflow Activity	17-6
Remove a Workflow Instance	17-7
Remove a Workflow Definition	17-7

18 Workflow Notifications

Create and Modify Notifications	18-1
Create a Notification	18-1
Create a Notification Recipient	18-2
Create a Notification Link	18-3
Check Out a Notification Definition	18-3
Modify a Notification Definition	18-4
Modify a Notification Instance	18-5
Send a Notification	18-5
Check In a Notification Definition	18-6
Remove a Notification Link	18-6
Remove a Notification Recipient	18-7
Remove a Notification	18-7

19 Setup Utilities

Initialize APIs	19-1
Initialize a Package	19-1
Verify Whether an API is Enabled	19-2
Enable an API	19-2
Disable an API	19-3
Get Factory Support	19-3
Get a Naming Version Object	19-3
Get a User ID	19-4
Get a User Name	19-4
Get Factory Utilities	19-5
Get a Base Object Type	19-5
Get a Company ID	19-6
Get Factory Validations	19-6
Validate a Namespace	19-6
Validate a Reference	19-7
Get Data from Object Naming Tables	19-8
Get the Latest Version	19-8
Get a Maximum Version	19-9
Get the Type of a Naming Object	19-9
Get an Object's Naming Version	19-10
Get an Object's Subtype ID	19-10
Get an Object's Checkout Status	19-11
Get Checkout Properties	19-12
Get a Naming Object's Parent	19-12
Get a Parent Naming Object	19-13
Get the Latest Version of the Parent Object	19-13
Get the Naming Status of a Parent Object	19-14
Get the Validation Status of a Parent Object	19-14
Get a Definition Object	19-15
Get a Lookup Meaning	19-16
Find Whether an Object is an Instance	19-16
Find Whether Checked Out By Current User	19-17
Find Whether a Checkout is User-Specific	19-17
Find Whether Checkout is Implicit	19-18
Define and Modify Adapters	19-18
Create an Adapter Domain	19-19
Modify an Adapter Domain	19-19

Create an Adapter Area	19-20
Modify an Adapter Area	19-21
Populate a Tech Type Table	19-22
Modify a Tech Type Table	19-22
Host Definition Constants	19-23
Read Messages	19-23
Get a Message	19-23
Get a Message Count	19-24
Initialize a Message Stack	19-24
Change Tablespaces	19-25

20 Execution Setups

Create and Modify Execution Setups	20-1
Create an Execution Setup	20-1
Check Out an Execution Setup	20-2
Modify an Execution Setup	20-3
Modify a Parameter	20-3
Modify an Execution Setup Parameter	20-4
Load Parameter Details	20-4
Copy an Execution Setup	20-5
Check In an Execution Setup	20-6
Submit an Execution Setup	20-6
Submit an Execution Setup for Instances	20-7
Submit an Execution Setup for Compound Objects	20-8
Upgrade an Execution Setup	20-10
Upgrade All Execution Setups	20-10
Make an Execution Setup Active	20-11
Remove an Execution Setup	20-11

21 Mappings

Create and Modify Mappings	21-1
Map a Column	21-1
Map a Table Descriptor to a Table Instance	21-2
Get a Table Instance ID	21-3
Create a Table Descriptor from a Table Instance	21-3
Create a Table Instance from a Table Descriptor	21-4
Modify a Mapping Column	21-4
Modify a Mapping at the Table Descriptor Level	21-5
Get a PPRREF_ID for an Executable in a Workflow	21-6
Get a PPRREF_ID for an Object in a Work Area	21-6

22 Outputs

Generate Outputs	22-1
Submit a Print Request	22-1
Get an Output's BLOB	22-2
Get an Output's CLOB	22-2

23 Version Labels

Modify Version Labels	23-1
Update a Version Label	23-1

24 Classification

Classify Objects	24-1
Classify an Object	24-1
Declassify an Object	24-2
Classify Subtypes	24-2
Get a Subtype Classification Level	24-3
Get an Object Classification Value	24-3
Get Child Terms	24-4
Create and Modify Classification Hierarchy Values	24-4
Insert a Classification Value	24-5
Update a Classification Value	24-5
Delete a Classification Value	24-6

25 Job Execution

Create and Execute Output LOBs	25-1
Create a Binary Output	25-1
Upload an Output BLOB	25-2
Upload an Output CLOB	25-2
Upload a LOB to a Temporary Table	25-3
Download a Job Output BLOB	25-4
Queue a Job	25-4
Wait for a Job to Complete	25-5
Generate an XML Payload	25-6
Retrieve Information about Ongoing Jobs	25-7
Get an Ongoing Job ID	25-7
Get Currently Executing Parameters	25-8

Get Information About a Job	25-8
Get Additional Job Information (Overloaded)	25-9
Set Execution Statuses	25-9
Set a User-specific Completion Status	25-10
Set a Customized Output Title	25-10
Set a Customized Output Subtitle	25-11
Set an Output Parameter	25-11
Get a Completion Status	25-12
Submit Messages	25-12
Submit a Message	25-12
Create Submission Records	25-13
Start a Job	25-13
Create a Submission, Get Job ID	25-14
Create a Submission	25-15
Add a Job Log	25-15

26 Security Policy

Create and Modify Security Policies	26-1
Create a Subtype	26-2
Copy a Subtype	26-2
Modify a Subtype	26-3
Assign Roles to a Subtype Operation	26-3
Assign Operations to a Subtype Role	26-4
Remove a Subtype	26-4
Create a Role	26-5
Modify a Role	26-5
Add a Group Role	26-6
Get Roles for a User	26-6
Remove a Role	26-7
Remove a Group Role	26-7
Create a User Group	26-8
Add Users to a Group	26-8
Remove Users from a Role in a User Group	26-9
Assign a User Group to an Object	26-9
Copy a User Group	26-10
Copy a User Group with its Users	26-11
Modify a User Group	26-11
Remove All Group Roles from a User Group	26-12
Remove All Users in a Group	26-12
Revoke a User Group From an Object	26-13
Undo a Revoke a User Group Action	26-13

Remove a User Group	26-14
Unassign a User Group From an Object	26-15
Unassign Roles from an Operation on an Object's Subtype	26-15
Unassign Operations on an Object Subtype's Role	26-16
Initialize Access to a Security View	26-16
Prevent Access to a Security View	26-17
Get the Resource Timeout Limit	26-18
Set the Resource Timeout Limit	26-18
Reset the Resource Timeout Limit	26-19

27 Validation

Validate Objects	27-1
Update an Object's Validation Status	27-1
Create and Modify Validation Supporting Documents	27-2
Create a Validation Supporting Document	27-2
Update a Validation Supporting Document	27-3
Obsolete a Validation Supporting Document	27-3

Part IV Oracle Life Sciences Data Management Workbench APIs

28 Introduction to Oracle DMW APIs

Set Up the Study Environment	28-1
Initialize a Study and Lifecycle	28-1
Create or Modify an Expression	28-2

29 Clinical Data Models

Create and Modify Clinical Data Models	29-1
Create a Study Clinical Data Model	29-2
Create a Study Clinical Data Model from a Library Model	29-3
Modify a Model's Name and Description	29-5
Check Out a Clinical Data Model	29-6
Check In a Clinical Data Model	29-6
Undo a Clinical Data Model Checkout	29-7
Install a Study Clinical Data Model	29-7
Promote a Clinical Data Model to Quality Control or Production	29-8
Remove a Clinical Data Model	29-9
Upgrade a Clinical Data Model to the Latest Library Model Version	29-9
Copy the Subject and/or Subject/Visit Table	29-10
Add a Table to a Clinical Data Model	29-10

Modify Table in Clinical Data Model	29-13
Remove Table from Clinical Data Model	29-13
Add a Column to a Table in a Clinical Data Model	29-14
Modify Column Display Characteristics in a Clinical Data Model Table	29-16
Modify a Column in a Clinical Data Model Table	29-18
Remove Column from Clinical Data Model Table	29-18
Add a Constraint to a Clinical Data Model Table	29-19
Modify a Constraint in a Clinical Data Model Table	29-20
Remove Constraint from a Clinical Data Model Table	29-21
Reorder Columns in a Clinical Data Model Table	29-21
Display Metadata Differences between Tables	29-22
Validate the Derived Encoding Date Through TMS	29-23
Get a Custom Listing Business Area ID for a Model	29-24
Required Profile for Custom Listing BAs	29-24

30 Codelists

Create and Modify Codelists	30-1
Create a Codelist	30-1
Modify a Codelist	30-2
Remove a Codelist	30-2
Check In a Codelist	30-3
Check Out a Codelist	30-3
Add Values to a Codelist	30-4
Remove Values from a Codelist	30-5
Get Codelist Details for a Given Column	30-5

31 Flags, Categories, and Actions

Flag-Related APIs	31-1
Set Flag	31-1
Get Flag	31-2
Get Flags on Data	31-3
Get Flags on Data Fuller	31-4
Delete Flag	31-4
Get Surrogate Key Values for Records in a Flag State	31-5
Flag Name-Related APIs	31-6
Get Flag Name Definition, Version 1	31-6
Get Flag Name Definition, Version 2	31-7
Get Flag Name Definitions	31-7
Get Flag States	31-8
Clinical Data Model Category-Related APIs	31-8

Create Model Flag Category Mapping	31-9
Get Categories for Model	31-9
Action-Related APIs	31-10
Create Discrepancy Action	31-10
Get Discrepancy Action, Version 1	31-11
Get Discrepancy Action, Version 2	31-11
Update Discrepancy Action	31-12
Delete Discrepancy Action	31-12

32 Transformations

Create and Modify Transformation Maps	32-1
Create Transformation Maps	32-2
Modify Transformation Maps	32-5
Mark Table Maps Not Used	32-7
Mark Column Maps Not Used	32-8
Check In Transformation Maps	32-8
Check Out Transformation Maps	32-9
Undo Checkout Transformation Map	32-10
Auto Map Tables	32-10
Accept Table Mappings	32-11
Auto Map Columns	32-11
Get MappedTo Target Columns	32-12
Accept Column Mappings	32-13
Upgrade Transformation Map	32-13
Install Transformation Map	32-14
Remove Transformation Map	32-15
Validate Transformation Maps	32-15
Update Validation Status	32-16
Execute Transformation Map	32-17
Validate Expression	32-17
Refresh Static Packages	32-18

33 Validation Checks

Create and Modify Validation Checks and Batches	33-1
Create a Validation Check Batch	33-1
Modify a Validation Check Batch	33-2
Remove Validation Check Batch	33-3
Create a Validation Check	33-3
Update a Validation Check	33-6
Install a Validation Check Batch	33-8

Submit a Validation Check Batch	33-9
Check In a Validation Check Batch	33-10
Check Out a Validation Check Batch	33-11
Undo Checkout For a Validation Check Batch	33-11
Update Validation Status of a Validation Check Batch	33-12
Upgrade a Validation Check Batch	33-12
Remove Validation Check(s)	33-13
Enable or Disable Validation Checks	33-13
Reorder Validation Checks	33-14

34 Data Loads

Submit Clinical One Data load	34-1
-------------------------------	------

Part V Public Views

35 Public Views

Clinical Data Model Views	35-1
DME_PUB_DATAMODEL_V	35-1
DME_PUB_TABLES_V	35-1
DME_PUB_COLUMNS_V	35-2
DME_PUB_CONSTRAINT_V	35-2
DME_PUB_CONSTRAINT_COLS_V	35-2
DME_PUB_LOV_VALUES_V	35-2
DME_PUB_COL_DISP_CHARS_V	35-2
DME_PUB_SDTM_COL_IDENTIFIERS_V	35-2
DME_PUB_SDTM_TAB_IDENTIFIERS_V	35-2
Codelist Views	35-2
DME_PUB_CODELIST_V	35-2
DME_PUB_CODELIST_VALUES_V	35-2
DME_PUB_XFM_FILTER_VALUES_V	35-2
Discrepancy Views	35-3
DME_PUB_DISCREPANCIES_V	35-3
DME_PUB_DISC_SEND_ERRORS_V	35-3
Validation Checks Views	35-3
DME_PUB_VC_BATCHES_V	35-3
DME_PUB_VC_DETAILS_V	35-3
Transformation Views	35-4
DME_PUB_DF_XFORM_MAP_V	35-4
DME_PUB_DF_MAP_ENTITY_V	35-4
DME_XFM_FILTER_VALUES_V	35-4

DME_PUB_XFM_SOURCE_TABLES_V	35-4
DME_PUB_XFM_SOURCE_COLUMNS_V	35-4
DME_PUB_XFM_TARGET_TABLES_V	35-4
DME_PUB_XFM_TARGET_COLUMNS_V	35-5
DME_PUB_XFM_AUTOMAPS_V	35-5
DME_PUB_XFM_COL_AUTOMAPS_V	35-5
DME_PUB_XFM_CUSTOM_PROGRAMS_V	35-5
DME_PUB_XFM_EXPR_STDFUNC_V	35-5
DME_PUB_XFM_EXPR_STATIC_PKGS_V	35-5
Thesaurus Management System-Related Views	35-5
DME_PUB_TMS_STUDY_DOM_ELEMS_V	35-5
DME_PUB_TMS_SETS_V	35-5
DME_PUB_TMS_SET_COLS_V	35-5
Generic Business Area Views	35-6
CDR_PUB_GENERIC_BA_V	35-6
CDR_PUB_GENERIC_BA_TABLES_V	35-6
Security-Related Views	35-6
CDR_PUB_UG_ROLES_V	35-6
CDR_PUB_USER_UG_ROLES_V	35-6
CDR_PUB_SUBTYPE_OPR_ROLES_V	35-6
CDR_PUB_OBJ_UG_V	35-6
Snapshot Label View	35-6
CDR_PUB_SNAPSHOT_LABEL_V	35-7

Preface

This guide contains information on using the Application Programming Interface (API) for Oracle Life Sciences Data Hub (Oracle LSH) and Oracle Life Sciences Data Management Workbench (Oracle DMW).

- [Documentation accessibility](#)
- [Related resources](#)
- [Diversity and Inclusion](#)
- [Access to Oracle Support](#)

Documentation accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Related resources

All documentation and other supporting materials are available on the [Oracle Help Center](#).

Diversity and Inclusion

Oracle is fully committed to diversity and inclusion. Oracle respects and values having a diverse workforce that increases thought leadership and innovation. As part of our initiative to build a more inclusive culture that positively impacts our employees, customers, and partners, we are working to remove insensitive terms from our products and documentation. We are also mindful of the necessity to maintain compatibility with our customers' existing technologies and the need to ensure continuity of service as Oracle's offerings and industry standards evolve. Because of these technical constraints, our effort to remove insensitive terms is ongoing and will take time and external cooperation.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Part I

Essential Information

This part of the Oracle Life Sciences Warehouse API guide contains the basic information you need on running APIs.

Part I contains the following chapters:

- [Using Application Programming Interfaces](#)
- [Reference Information](#)
- [Access to Private Oracle DMW and Oracle LSH Tables](#)

1

Using Application Programming Interfaces

All Oracle Life Sciences Data Hub (Oracle LSH) views are public and have names that begin with "cdr_". You can see them in SQL Developer or a similar tool, or query for them using the string `cdr_`



Note:

During its initial development, Oracle LSH was known as CDR. Therefore many internal names contain the string `cdr`. Please think of CDR as a synonym for Oracle LSH.

This section contains the following topics:

- [About APIs](#)
- [Tips](#)
- [Calling APIs from Outside Oracle LSH](#)
- [Calling APIs from Defined Programs](#)
- [Code Example Using Security and Error Message APIs](#)

About APIs

Oracle LSH includes a set of APIs that enable you to do most of the things you can do through the user interface, including creating, modifying, and installing objects.

You can call Oracle LSH APIs from source code in a defined Program in Oracle LSH. In this case, no additional security or setup is required.

If you have an Oracle LSH database account with certain privileges, you can also develop programs that call APIs in a tool outside of Oracle LSH; such as SAS, Oracle SQL Developer, or SQL*Plus. You can then see views of all the Oracle LSH data you need, including data from both the LSH (CDR) schema and, for classification data, the TMS schema. You can make the programs you write available to other people from the external tool. See [Calling APIs from Outside Oracle LSH](#).

This section contains the following topics:

- [Example 1: Using APIs to Perform Multiple Tasks at Once](#)
- [Example 2: Calling APIs from an External System's UI](#)
- [Understand Oracle LSH Functionality](#)

Example 1: Using APIs to Perform Multiple Tasks at Once

You can write a package that calls multiple APIs to do with one execution what it would take many tasks in the user interface (UI) to do; for example, create a Domain, an Application Area

inside the Domain, a Work Area inside the Application Area, and multiple Load Sets, Tables, and Programs, each with a definition in the Application Area and an instance in the Work Area, and install the Work Area. If you have a standard structure for Project/Therapeutic Area Domains, for example, you may want to work this way. However, remember that you can also copy a Domain and all its contents at once in the user interface.

Using APIs is even more attractive when you want to create, for example, multiple objects with variations or large complex objects such as Report Sets. You can create a spreadsheet to store all the variable information and load its data into an Oracle LSH Table instance using a Text Load Set. In your program, use a loop to read all the spreadsheet data and call the relevant Oracle LSH APIs to create the objects.

Example 2: Calling APIs from an External System's UI

Example 2: Calling APIs from an External System's UI: You may want to allow people in your company to perform actions on Oracle LSH objects from an external system.

For example, instead of requiring that SAS developers check out Source Code in Oracle LSH before opening the SAS IDE from an Oracle LSH Program, you may want to add a button to the SAS user interface that calls the API for checking out the Source Code object when clicked. Then, if the program is located in a schema with Execute privileges on the security API, any user with SAS, a database account in Oracle LSH, and normal Oracle LSH object security privileges on the Source Code definition, can check out the Source Code definition directly from SAS.

Understand Oracle LSH Functionality

To use Oracle LSH APIs, you must understand basic Oracle LSH functionality including:

- **Object Ownership.** You must create container objects before creating the objects they contain, because to create any object you must identify its namespace (parent or container) object. For example, begin by defining a Domain, then an Application Area, then a Work Area, and then create a Table definition in the Application Area and an instance of it in the Work Area. You can use a single API to create both the Table definition and an instance of it. For details, see "Object Ownership" in the *Oracle Life Sciences Data Hub Application Developer's Guide*.
- **Installation.** You must create an instance of an object definition and install it before you can execute or store data in the object.
- **Mapping.** All executable objects must contain one Table Descriptor for each Table instance they read from and write to, and the Table Descriptors and Table instances must be mapped. For details, see "Defining and Mapping Table Descriptors" in the *Oracle Life Sciences Data Hub Application Developer's Guide*.
- **Checking Objects In and Out.** You must check objects out to modify them and check them in before you install and use them. For details, see "Understanding Object Versions and Checkin/Checkout" in the *Oracle Life Sciences Data Hub Application Developer's Guide*.
- **Security.** All objects require user group assignments to control user access. For details, see "Applying Security to Objects and Outputs" in the *Oracle Life Sciences Data Hub Application Developer's Guide*.
- **Classification.** To enable objects to appear in the Reports tab of the user interface for end users to run them and view their outputs, you must classify them. Classifications can also be used in searching for objects. For details, see "Classifying Objects and Outputs" in the *Oracle Life Sciences Data Hub Application Developer's Guide*.

- **Validation.** Objects should be validated according to your company policy whether they are created in the user interface or with APIs. For details, see "Validating Objects and Outputs" in the *Oracle Life Sciences Data Hub Application Developer's Guide*.
- **Object-Specific Information.** Further information on each object type is included in other chapters of the *Oracle Life Sciences Data Hub Application Developer's Guide*.

Tips

The section provides advice on committing APIs and getting attribute values for namespace objects. It contains the following topics:

- [Committing APIs](#)
- [Get Attribute Values for Namespace Objects](#)

Committing APIs

The standard parameter P_COMMIT is found in every API; see [Standard Parameters](#). Its default value is FALSE, which prevents the API from committing. This is useful if you are creating multiple objects in a single program execution, to enable you to do a rollback. However, if you want the API to commit, pass the value `FND_API.G_TRUE`.

Get Attribute Values for Namespace Objects

Many APIs require internal IDs for the namespace object of the object you are creating. Use [Get a Naming Version Object](#) to get these details. However, you must first determine what the namespace object is, using the object ownership diagram and explanation in the *Oracle Life Sciences Data Hub Application Developer's Guide* or *Oracle Life Sciences Data Management Workbench Study Setup Guide*, then query for the namespace object ID and object version using its name and its namespace's name and object type, in CDR_DF_NAMING_V.

Calling APIs from Outside Oracle LSH

This section contains the following topics:

- [Security Setup Required](#)
- [Calling the Security API Package](#)
- [Calling APIs from SAS](#)
- [Using a Permanent Schema for Deploying Programs that Call APIs](#)

Security Setup Required

To run any API package from a tool outside of Oracle LSH, such as SAS, SQL Developer, or SQL*Plus, your system administrator needs to do the following:

1. Set up an Oracle LSH database account linked to your Oracle LSH user account; see "Creating Database Accounts" in the *Oracle Life Sciences Data Hub System Administrator's Guide*.
2. Grant your Oracle LSH database account Execute privileges on the API security package CDR_PUB_API_INITIALIZATION.

3. To run APIs that insert, delete, or modify Oracle LSH classification hierarchy terms, you need security access to the Oracle Thesaurus Management System (TMS) instance that is installed as part of Oracle LSH. The Oracle LSH classification system is based on TMS.

 Note:

This step is not required for Oracle DMW custom programs. Oracle DMW does not use the Oracle LSH classification system.

Ask your system administrator to run the script `tmsadduser.sql` to do the following:

- Create a TMS user account with the same name as your Oracle LSH database account so that your account is entered in the TMS_ACCOUNTS and OPA_ACCOUNTS tables.
- Give your TMS user account superuser privileges in the TMS_ACCOUNTS table.
- Grant your TMS user account the TMS_MAINTAIN_PRIV database role.

Calling the Security API Package

For every program that you run from outside Oracle LSH to call an Oracle LSH API, you must first call a special security API: CDR_PUB_API_INITIALIZATION. This API contains three functions:

- EnableApis
- DisableApis
- AreApisEnabled

When you initialize any API, the AreApisEnabled function of the security API, CDR_PUB_API_INITIALIZATION, is called to check the calling program. If the program does not have the EnableApis flag set to True, the initialization fails.

To set the EnableApis flag to True, call the EnableApis function from your program. To call the EnableApis function, you need a schema/user account with an Execute privilege on the CDR_PUB_API_INITIALIZATION API granted by a system administrator.

Therefore, when you write a program that calls an API and is intended for use outside Oracle LSH, set the EnableApis flag to True in your program and then set it to False at the end to force the security check on the schema the next time the program is run:

1. Begin the body with the following code to call the function to enable APIs:

```
call CDR_PUB_API_INITIALIZATION.enableApis (arguments);
```

The arguments are described in CDR_PUB_API_INITIALIZATION itself.

2. At the end of the body, disable APIs with the following code:

```
CDR_PUB_API_INITIALIZATION.disableApis (arguments);
```

See [Example 1-1](#).

Calling APIs from SAS

If you need to call multiple APIs from SAS, you may want to use a PL/SQL wrapper around the API calls so that you only call PL/SQL once. The *Oracle Life Sciences Data Hub Application Developer's Guide* has two examples. In the Report Sets chapter, see "Passing Values from a

Program Instance to the Report Set for Post-Processing" and in the Programs chapter see "Calling an API to Capture Output Parameter Values."

Using a Permanent Schema for Deploying Programs that Call APIs

Starting release 3.1, if you have custom user defined outside of Oracle LSH, make sure that the schema is editioned. Use the following command to mark any existing custom users/schemas as editionable:

```
ALTER USER <user_name> ENABLE EDITIONS FORCE;
```

When you develop a program outside Oracle LSH that will call the Oracle LSH APIs, you can use your own schema in the external tool (such as SQL*Plus, SQL Developer, or SAS) to run and test the program, if you have Execute privileges on CDR_PUB_API_INITIALIZATION. When you are ready to allow other people to run it, copy it into a different location.

Oracle recommends setting up one or more permanent, publicly available schemas in the Oracle LSH database for the purpose of compiling and storing programs that call the Oracle LSH APIs. Grant each schema Execute privileges on CDR_PUB_API_INITIALIZATION. This approach has the following advantages:

- If a user manually runs your program, he or she must enter the program location and name explicitly. This will be much easier if the user knows which schema contains such programs.
- If you set up the program to run automatically when a user clicks a button in the external system's user interface, for example, you must hardcode the program's name and location into the code.
- You can grant Execute on CDR_PUB_API_INITIALIZATION to a controlled number of schemas.

Calling APIs from Defined Programs

If you develop and run a Program that calls an API within Oracle LSH—that is, in the defined Source Code of a defined Program object—no security is required beyond normal Oracle LSH object security. You do not need Execute privileges on the CDR_PUB_API_INITIALIZATION API, and you do not need to enable APIs in your Program code.



Note:

Within Oracle LSH, the calls to CDR_PUB_API_INITIALIZATION are unnecessary and in fact a program that includes such a call will not compile because the Work Area schema does not have Execute privileges on CDR_PUB_API_INITIALIZATION.

You do need to install the Program before you can run it, as you do any defined Program in Oracle LSH.

You can write packages in an Oracle LSH Program that do anything with APIs that you could do in a package outside Oracle LSH. For example, you could create an instance of a Program definition whose Source Code created a Work Area, several Load Sets, and a Program to merge the data, instead of defining the Work Area, Load Sets and Program through the Oracle LSH user interface.

Code Example Using Security and Error Message APIs

There are two utility Oracle LSH APIs that you call in conjunction with other Oracle LSH APIs:

- **CDR_PUB_API_INITIALIZATION.** This API is required for developing and running programs that call any Oracle LSH API from outside Oracle LSH. See [Calling the Security API Package](#) for further information.
- **CDR_PUB_MSG_PUB.** This API returns error messages from other Oracle LSH APIs called in the same package.

The following code provides an example of calling the API to define a Work Area and each of the utility APIs.

Example 1-1 Program that Calls the API to Define a Work Area and Calls the Security and Error Message APIs

```
CDR_PUB_DF_WORKAREA.CREATEWORKAREA (
    P_API_VERSION=>1,
    P_INIT_MSG_LIST=>CDR_PUB_DEF_CONSTANTS.G_FALSE,
    P_COMMIT=>CDR_PUB_DEF_CONSTANTS.G_FALSE,
    P_VALIDATION_LEVEL=>CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
    X_RETURN_STATUS => X_RETURN_STATUS,
    X_MSG_COUNT      => X_MSG_COUNT,
    X_MSG_DATA       => X_MSG_DATA,
    PIO_SOURCECDRNAMING =>VARWANSOBJ,
    PIO_WORKAREAOBJTYPE =>VARWAOBJ,
    PI_DEFCLASSIFICATIONCOLL => NULL);
    IF X_RETURN_STATUS <> 'S' THEN
        DBMS_OUTPUT.PUT_LINE('ERROR FOUND IN CREATEPROGRAM');
    END IF ;
    X_MSG_COUNT := CDR_PUB_MSG_PUB.COUNT_MSG(
        P_API_VERSION=>1,
    P_INIT_MSG_LIST=>CDR_PUB_DEF_CONSTANTS.G_FALSE,
    P_COMMIT=>CDR_PUB_DEF_CONSTANTS.G_FALSE,
        P_VALIDATION_LEVEL=>CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
    );
    IF X_MSG_COUNT >= 1 THEN
        FOR I IN 1..X_MSG_COUNT LOOP
            IF I =1 THEN
                X_MSG_DATA := CDR_PUB_MSG_PUB.GET(
                    P_API_VERSION=>1,
                    P_INIT_MSG_LIST=>CDR_PUB_DEF_CONSTANTS.G_FALSE,
                    P_COMMIT=>CDR_PUB_DEF_CONSTANTS.G_FALSE,
                    P_VALIDATION_LEVEL=>CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
                    P_MSG_INDEX =>CDR_PUB_MSG_PUB.G_FIRST,
                    P_ENCODED =>CDR_PUB_DEF_CONSTANTS.G_FALSE);
            ELSIF I = X_MSG_COUNT THEN
                X_MSG_DATA := CDR_PUB_MSG_PUB.GET(
                    P_API_VERSION=>1,
                    P_INIT_MSG_LIST=>CDR_PUB_DEF_CONSTANTS.G_FALSE,
                    P_COMMIT=>CDR_PUB_DEF_CONSTANTS.G_FALSE,
                    P_VALIDATION_LEVEL=>CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
                    P_MSG_INDEX =>CDR_PUB_MSG_PUB.G_LAST,
                    P_ENCODED =>CDR_PUB_DEF_CONSTANTS.G_FALSE);
            ELSE
                X_MSG_DATA := CDR_PUB_MSG_PUB.GET(
                    P_API_VERSION=>1,
                    P_INIT_MSG_LIST=>CDR_PUB_DEF_CONSTANTS.G_FALSE,
                    P_COMMIT=>CDR_PUB_DEF_CONSTANTS.G_FALSE,
                    P_VALIDATION_LEVEL=>CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
```

```

P_MSG_INDEX =>CDR_PUB_MSG_PUB.G NEXT,
P_ENCODED =>CDR_PUB_DEF_CONSTANTS.G_FALSE);
    END IF ;
    DBMS_OUTPUT.PUT_LINE('MESSAGE:'||I ||' : '|| X_MSG_DATA);
END LOOP;
END IF;
CDR_PUB_API_INITIALIZATION.DISABLEAPIS(
    P_API_VERSION=>1,
    P_INIT_MSG_LIST=>CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT=>CDR_PUB_DEF_CONSTANTS.G_FALSE,
    P_VALIDATION_LEVEL=>CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS => X_RETURN_STATUS,
X_MSG_COUNT      => X_MSG_COUNT,
X_MSG_DATA       => X_MSG_DATA);
EXCEPTION
WHEN OTHERS THEN
    CDR_PUB_API_INITIALIZATION.DISABLEAPIS(
        P_API_VERSION=>1,
        P_INIT_MSG_LIST=>CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT=>CDR_PUB_DEF_CONSTANTS.G_FALSE,
        P_VALIDATION_LEVEL=>CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS => X_RETURN_STATUS,
X_MSG_COUNT      => X_MSG_COUNT,
X_MSG_DATA       => X_MSG_DATA);
END MY_PROCEDURE;

BEGIN -- PACKAGE INIT BLOCK
CDR_PUB_API_INITIALIZATION.ENABLEAPIS(
    P_API_VERSION=>1,
    P_INIT_MSG_LIST=>CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT=>CDR_PUB_DEF_CONSTANTS.G_FALSE,
    P_VALIDATION_LEVEL=>CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS => X_RETURN_STATUS,
X_MSG_COUNT      => X_MSG_COUNT,
X_MSG_DATA       => X_MSG_DATA);
END MY_PACKAGE;

```

2

Reference Information

This section contains the following topics:

- [CDR Naming Version Object Type](#)
- [CDR Base Object Type](#)
- [CDR Object-Specific Database Object Types](#)
- [Retrieving Reference Codelist Names and Values](#)
- [Retrieving the Instance Domain ID](#)
- [Retrieving the ID of a User-Defined Domain](#)
- [CDR_DF_NAMING_V View](#)
- [Standard Parameters](#)

CDR Naming Version Object Type

Object information is stored in two tables in the Oracle LSH database: `cdr_namings`, which contains one row for each defined Oracle LSH object, and `cdr_naming_versions`, which contains one row for each version of each defined Oracle LSH object. Information from these two tables is stored in two composite database object types: `cdr_naming_version_obj_type` and `cdr_base_obj_type`.

For both the composite object types, the attributes `company_id`, `obj_id`, `obj_ver`, `namespace_obj_id`, and `namespace_obj_ver` form a composite primary key. You can refer to any existing object using this primary key.

Parameters of type `cdr_naming_version_obj_type` are required in APIs for creating and modifying an object. To get an object's naming version attribute values, see [Get a Naming Version Object](#).

The attributes of `cdr_naming_version_obj_type` are:

- **company_id**. To get your company ID, use `CDR_PUB_DEF_FACTORY_UTILS.GetCompanyId`.
- **obj_id** is the unique ID of the object. Oracle LSH generates this ID when you create a new object. Enter NULL if you are creating a new object.
- **obj_ver** is the object's version number. Enter NULL if you are creating a new object.

Note:

The attributes `company_id`, `obj_id`, `obj_ver`, `namespace_obj_id`, and `namespace_obj_ver` together constitute an object's primary key.

- **namespace_obj_id**. The unique ID of the object's parent object; for example, a Table instance is always contained in a Work Area, so its `namespace_obj_id` is the object ID of its Work Area.

- **namespace_obj_ver**. The version number of the object's parent object.

 Note:

You can create a child object only in the latest version of its parent object. If you pass a namespace version number that is not the latest when creating a child object, the system ignores the value you pass and creates the child in the latest version of the parent.

- **namespace_start_obj_ver**. This attribute contains the version number of the parent object at the time the version represented by **obj_ver** of the object represented by **obj_id** was created.
- **namespace_end_obj_ver**. This attribute contains the version number of the parent object at the time when the version represented by **obj_ver** of the object represented by **obj_id** was superseded by a higher version. If the object is still the most current version, then this attribute contains the value 999999. If you are creating a new object, enter 999999.
- **object_type_rc**. This attribute defines what type of object you are creating or modifying. This value is mandatory for creating objects, but not for modifying objects. See [Retrieving Reference Codelist Names and Values](#) for information on retrieving valid values.
- **name**. This is the name of the object.
- **owning_location_rc**. This attribute is entered in the system at LSH installation time and is stored as a profile in the system. The system automatically sets this value to the profile value for all objects. Enter NULL.
- **checked_out_flag_rc**. This value indicates whether the object is currently checked out or not. The possible values are \$YESNO\$YES and \$YESNO\$NO. If you are creating a new object, enter NULL.
- **checked_out_id**. This is the user ID of the person who checked out the object, if it is currently checked out. If you are creating a new object, enter NULL.
- **object_subtype_id**. This attribute specifies the ID of the object's subtype. Use CDR_PUB_DF_NAMING_UTIL.GetObjectSubtypeID to retrieve an object's subtype ID. If you are creating a new object, enter NULL.
- **description**. This is an optional attribute but it is highly recommended that you provide a description for future reference. You can modify the description using appropriate API for the object.
- **ref_company_id**. If the object is an instance object, this attribute contains the company ID of the source definition.
- **ref_obj_id**. If the object is an instance object, this attribute contains the object ID of the source definition.
- **ref_obj_ver**. If the object is an instance object, this attribute contains the object version number of the source definition.
- **copied_from_company_id**. If the object is a copy of another object, this attribute contains the company ID of the original object. If you are creating a new object, enter NULL.
- **copied_from_obj_id**. If the object is a copy of another object, this attribute contains the object ID of the original object. If you are creating a new object, enter NULL.
- **copied_from_obj_ver**. If the object is a copy of another object, this attribute contains the object version number of the original object. If you are creating a new object, enter NULL.

- **object_version_number**. This attribute is for Oracle LSH internal use only. Never enter a value for this attribute. If you are creating a new object, enter NULL.
- **status_rc**. This attribute contains the current status of the object. See [Retrieving Reference Codelist Names and Values](#) for information on retrieving valid values. If you are creating a new object, enter NULL.
- **validation_status_rc**. This attribute contains the current validation status of the object. See [Retrieving Reference Codelist Names and Values](#) for information on retrieving valid values. If you are creating a new object, enter NULL.
- **version_label**. This attribute stores the version label of the object, if any. If you are creating a new object, enter NULL.

CDR Base Object Type

For some operations on objects, only the identification contained in a CDR base object type (`cdr_base_obj_type`) is required. Some APIs allow you to operate on multiple objects at the same time by using a parameter based on a collection of CDR base object types called `cdr_base_obj_coll`.

A CDR Base Object Type contains a subset of the information contained in a CDR naming Version Object Type. (See [CDR Naming Version Object Type](#).)

CDR Object-Specific Database Object Types

Each Oracle LSH object type has its own unique attributes beyond what is included in the CDR Naming Version Object Type and CDR Base Object Type. These unique attributes are included in a view for each object type. The view includes information on both definitions and instances of a particular object type. In the case of Tables, it includes Table Descriptors as well as Table definitions and instances.

APIs that are used to create or modify Oracle LSH defined objects contain parameters based on these supplementary database object types. You can set values for the object-specific attributes using these parameters.

For example, the supplementary database object type for Oracle LSH Programs is called `cdr_program_obj_type`. In the Create Program API, the parameter `pi_cdrprgobjtype` is of this type. Its attributes are:

- **company_id**. To get your company ID, use `CDR_PUB_DEF_FACTORY_UTILS.GetCompanyId`.
- **obj_id**. The unique ID of the Program.
- **obj_ver**. The Program's version number.
- **tech_type_id**. Different executable object types have different technology types, which can be queried using the view `cdr_tech_types_v`. Use the column `program_type_rc` to see which tech type is valid for a particular object type. In the case of Programs, only the tech types whose value in the `program_type_rc` column is `$PROGRAMTYPES$PROGRAM` and which are present in the lookup type `cdr_tech_types` are allowed. They are: `$TECHTYPES$SAS`, `$TECHTYPES$SASCATALOGS`, `$TECHTYPES$SASFORMATS`, `$TECHTYPES$PLSQL`, `$TECHTYPES$REPORTS`.

 Note:

Tech types that are not included in the lookup type `cdr_tech_types` are used internally only and should not be used with public APIs.

- **manual_validation_flag_rc.** This flag determines whether a Program's outputs receive their validation status from their Execution Setup or must be validated manually. The valid values are: `$YESNO$YES` and `$YESNO$NO`.

See the chapter on "Defining Programs" in the *Oracle Life Sciences Data Hub Application Developer's Guide* for information about these attributes. Each object type has its own chapter in this manual where its attributes are described.

Retrieving Reference Codelist Names and Values

Some database object type attributes (those ending in the string `_rc`) have a fixed set of allowed values stored in a lookup (reference codelist). These attributes correspond to fields in the user interface with a drop-down or pop-up list of values. To supply or change one of these values you must enter the exact string stored in the reference codelist, with the codelist name surrounded by dollar signs and followed by a codelist value.

For example, the API to create any object includes a parameter of type `cdr_naming_version_obj_type`, one of whose attributes is `object_type_rc`. You must enter the correct string for the type of object you want to create.

Reference codelists are stored in a table you access through the view `cdr_lookups`. The following columns contain the following information:

- **lookup_type:** reference codelist names
- **lookup_code:** reference codelist values
- **meaning:** the text that is displayed in the user interface
- **description:** additional information (sometimes)

If you have LSH Setup Admin privileges you can look up reference codelists in the Applications user interface; see "Querying and Viewing Lookups" in the *Oracle Life Sciences Data Hub System Administrator's Guide*.

You can browse the view in a tool like SQL Developer to find these values. However, it is not always easy to guess the name of the reference codelist. In that case, you can go into the Oracle LSH user interface to where they are displayed and note one of the allowed values, then query.

For example, object types are displayed in the Add drop-down list in the Work Area Properties screen. You can see that one object type is Business Area, so you can use the following query:

```
select lookup_type, lookup_code, meaning from cdr_lookups where meaning like  
'%Business Area%';
```

Now you know that the `lookup_type` for object types is `CDR_OBJECT_TYPES` and you can use the following query to get all the other values:

```
select distinct lookup_code, meaning from cdr_lookups where lookup_type =  
'CDR_OBJECT_TYPES';
```

Retrieving the Instance Domain ID

While working with classification-related APIs, you may need the domain ID for the Oracle LSH environment you are working in. This is the ID for your Oracle LSH instance, which is created during installation. It has nothing to do with user-defined Domains that contain Application Areas.

Its value is usually 1.

Retrieving the ID of a User-Defined Domain

Query the CDR_DF_NAMING view for the domain ID and other attributes.

```
select * from cdr_df_naming_v where object_type_rc like '%$objtypes$libdomain%';
```

CDR_DF_NAMING_V View

Query the CDR_DF_NAMING_v view for object types.

```
select distinct OBJECT_TYPE_RC, from cdr_df_naming_v;
```

Then query for the object type you need, for example:

```
select * from cdr_df_naming_v where object_type_rc like '%$objtypes$object_type%';
```

Standard Parameters

Some or all of the following standard Oracle Applications parameters are included in each function and procedure:

P_API_VERSION

(Mandatory) Enter 1.

P_INIT_MSG_LIST

(Optional) Accept the default value (FND_API.G_FALSE) to ensure that this individual API does not initialize the message list when the procedure is entered. Pass FND_API.G_TRUE to override the default behavior.

P_COMMIT

(Optional) Accept the default value (FND_API.G_FALSE) to ensure that this individual API does not commit upon completion. Pass FND_API.G_TRUE to override the default behavior.

P_VALIDATION_LEVEL

(Optional) Accept the default value to perform full validation. No other values are currently supported.

X_RETURN_STATUS

This output parameter returns the end status of the API: (S) Success, (E) Error or (U) Unexpected Error.

X_MSG_COUNT

This output parameter returns the count of error messages if the return status is other than Success.

X_MSG_DATA

This output parameter returns the text of the error message, if the message count is 1. If there are more than one messages, use `cdr_pub_msg_pub.get` to retrieve the messages.

3

Access to Private Oracle DMW and Oracle LSH Tables

The published and public interfaces (consisting of views and APIs) always act as the first and recommended method for accessing the data stored in the application tables of Oracle DMW and Oracle LSH. Public interfaces have been tested and secured to ensure that the information retrieved from those methods are accurate, secure, and provided in a manner that is supported, safe, and does not have any negative impact in the performance or operations on the application.

Accessing the private tables of Oracle DMW and Oracle LSH is not a recommended practice. If the private tables are used, it is highly recommended to monitor the load and impact of any queries executed against the private tables. In addition, note the following caveats:

- Private tables may change from one release to the next.
- Grants on the private objects may be lost during the upgrades and have to be regranted.
- The usage of private objects can cause performance issues in the database.

Part II

Object APIs

This part of the Oracle Life Sciences Warehouse API guide contains APIs that you can use to create, modify, check in or out, delete, copy, and move defined Oracle LSH objects. You can also perform object-specific tasks using these APIs.

Part II contains the following chapters:

- [Application Areas](#)
- [Business Areas](#)
- [Data Marts](#)
- [Domains](#)
- [Load Sets](#)
- [Parameter Sets](#)
- [Planned Outputs](#)
- [Programs](#)
- [Software Source Codes](#)
- [Tables](#)
- [Parameters](#)
- [Variables](#)
- [Work Areas](#)
- [Workflows](#)
- [Workflow Notifications](#)

4

Application Areas

This is a public interface for Application Area-related operations— creating, modifying, and removing Application Areas; as well as copying and moving object definitions into an Application Area. It contains the following:

- [Define and Modify Application Areas](#)

Define and Modify Application Areas

This section contains the following topics:

- [Create an Application Area](#)
- [Modify an Application Area](#)
- [Remove an Application Area](#)
- [Copy Objects into an Application Area](#)
- [Move Objects into an Application Area](#)

Create an Application Area

Use this API to create a new Application Area.

Name

CDR_PUB_DF_APPLICATIONAREA.CreateApplicationArea

Signature

```
PROCEDURE CREATEAPPLICATIONAREA(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  X_RETURN_STATUS OUT VARCHAR2,  
  X_MSG_COUNT OUT NUMBER,  
  X_MSG_DATA OUT VARCHAR2,  
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,  
  PI_DEFCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values for the Application Area you want to create.
The following attributes are required: company_id, namespace_obj_id, namespace_obj_ver, object_type_rc. for object_type_rc enter \$objtypes\$appliance.

- **PI_DEFCLASSIFICATIONCOLL**(Optional) By default the new Application Area is classified according to the subtype you assigned it in the CDR_NAMING_VERSION_OBJ_TYPE. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID. If you want the Application Area to inherit its classifications for a particular level from its parent Domain, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero). If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are not relevant to Application Areas. Do not enter any values for them.

Modify an Application Area

Use this API to modify the name or description of an existing Application Area.

Name

CDR_PUB_DF_APPLICATIONAREA.ModifyApplicationArea

Signature

```
PROCEDURE MODIFYAPPLICATIONAREA(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) as well as the following:

PIO_SOURCECDRNAMING (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Application Area you want to modify and for the attributes you want to modify. You can modify the name and description. All attributes are required.

Remove an Application Area

Use this API to remove one or more Application Areas and all its/their contents.

Name

CDR_PUB_DF_APPLICATIONAREA.RemoveApplicationAreas

Signature

```
PROCEDURE REMOVEAPPLICATIONAREAS(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
```

```

X_MSG_DATA OUT VARCHAR2,
PI_BASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PI_BASEOBJCOLL (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES. For each Application Area that you want to remove (including all its contents), initialize a CDR_BASE_OBJ_TYPE and then extend the collection.

The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.

Copy Objects into an Application Area

Use this API to copy object definitions into an Application Area.

Name

CDR_PUB_DF_APPLICATIONAREA.CopyObjectIntoAA

Signature

```

PROCEDURE COPYOBJECTINTOAA(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_CDRBASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL,
  PI_CDRTARGETCONTAINEROBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PI_CHECKINFLAG IN VARCHAR2
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_CDRBASEOBJCOLL** (Mandatory). This is a collection of CDR_BASE_OBJ_TYPES. For each object that you want to copy into the Application Area, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.
The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.
- **PI_CDRTARGETCONTAINEROBJECT** (Mandatory). This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Application Area into which you want to copy objects.
The following attributes are required: COMPANY_ID, OBJECT_ID, OBJECT_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_VERSION_NUMBER.
- **PI_CHECKINFLAG** (Mandatory). Enter \$YESNO\$NO if you want any checked-out copied objects to remain checked out, or \$YESNO\$YES if you want the system to check them in after the copy operation.

Move Objects into an Application Area

Use this API to move LSH objects into an Application Area.

Name

CDR_PUB_DF_APPLICATIONAREA.MoveObjectIntoAA

Signature

```
PROCEDURE MOVEOBJECTINTOAA (
    P_API_VERSION IN NUMBER,
    P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
    P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
    P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
    X_RETURN_STATUS OUT VARCHAR2,
    X_MSG_COUNT OUT NUMBER,
    X_MSG_DATA OUT VARCHAR2,
    PI_CDRBASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL,
    PI_CDRTARGETCONTAINEROBJECT IN OUT CDR_BASE_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_CDRBASEOBJCOLL** (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES. For each object that you want to move into the Application Area, initialize a CDR_BASE_OBJ_TYPE and then extend the collection. The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.
- **PI_CDRTARGETCONTAINEROBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Application Area into which you want to move objects. The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.

5

Business Areas

This section contains the following topics:

- [Define and Modify Business Areas](#)
- [Create and Modify Business Area Hierarchies](#)
- [Create and Modify Business Area Joins](#)
- [Public APIs and Naming Views for Generic Visualization Adapter \(GVA\)](#)

Define and Modify Business Areas

This is a public interface for Business Area-related APIs, including creating, modifying, and removing Business Areas. It also includes APIs for checking Business Areas in and out, and undoing a Business Area checkout.

This section contains the following topics:

- [Create a Business Area](#)
- [Modify a Business Area](#)
- [Check Out a Business Area](#)
- [Undo a Business Area Checkout](#)
- [Check In a Business Area](#)
- [Remove a Business Area](#)

Create a Business Area

Use this API to create a new Business definition, a new instance of an existing Business Area definition, or a new definition and an instance of it.

Name

CDR_PUB_DF_BUSINESSAREA.CreateBusiArea

Signature

```
PROCEDURE CREATEBUSIAREA(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  X_RETURN_STATUS OUT VARCHAR2,  
  X_MSG_COUNT OUT NUMBER,  
  X_MSG_DATA OUT VARCHAR2,  
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,  
  PI_CDRPRGOBJTYPE IN CDR_BUSAREA_OBJ_TYPE,  
  PI_CREATEOBJECT IN VARCHAR2,  
  PI_INSTANCE_SUBTYPE_ID IN CDR_NAMINGS.OBJECT_SUBTYPE_ID%TYPE,  
  PI_DEFCCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL,
```

```
PI_INSTCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. If you are creating a new definition only or a new definition and an instance of it, enter values for the new definition.

If you are creating an instance of an existing definition, enter values to identify the definition. For OBJECT_TYPE_RC enter \$OBJTYPES\$BUSAREA if you are creating a definition only; \$OBJTYPES\$BUSAREAREF if you are creating an instance of an existing definition; and NULL if you are creating a new definition and an instance of it.
- PI_CDRPRGOBJTYPE** (Optional) This is a parameter of table type CDR_BUSAREA_OBJ_TYPE specific to Business Areas. If you are creating a new definition, enter values for the new Business Area.

The following attributes are required:
ADAPTER_COMPANY_ID, ADAPTER_OBJ_ID, ADAPTER_OBJ_VER.

If you are creating an instance of an existing Business Area, do not enter any values here.
- PI_CREATEOBJECT** (Mandatory) Enter DEFN to create a definition only; INST to create an instance of an existing definition; or BOTH to create a new definition and an instance of it.
- PI_INSTANCE_SUBTYPE_ID** (Optional) If you are creating a new instance, enter the ID for the subtype you want to give the instance. If you are creating a definition only, do not enter a value for this parameter.
- PI_DEFCLASSIFICATIONCOLL** (Optional) By default, the new definition is classified according to the subtype you assigned it in the CDR_NAMING_VERSION_OBJ_TYPE. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID.

If you want the definition to inherit its classifications for a particular level from its parent, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are not relevant to Business Areas. Do not enter any values for them.
- PI_INSTCLASSIFICATIONCOLL** (Optional) By default, the new instance is classified according to the subtype you assigned it in the PI_INSTANCE_SUBTYPE_ID. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID.

If you want the instance to inherit its classifications for a particular level from its parent Work Area, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are not relevant to Business Areas. Do not enter any values for them.

Modify a Business Area

Use this API to modify a Business Area definition or instance.



Note:

If you are modifying a definition, you must first check it out.

Name

CDR_PUB_DF_BUSINESSAREA.ModifyBusiAreaDetails

Signature

```
PROCEDURE MODIFYBUSIAREADETAILS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_CDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_CDRNAMING (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Business Area and enter new values for the attributes you want to modify.

You can change the name, description, or version label for either a definition or instance. For an instance, you can also change to a different underlying source definition by entering values for the new definition in the three REF attributes. All attributes are required.

Check Out a Business Area

Use this API to check out a Business Area definition either directly or through an instance of it.

Name

CDR_PUB_DF_BUSINESSAREA.CheckOutBusiArea

Signature

```
PROCEDURE CHECKOUTBUSIAREA (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_BASEOBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PI_COMMENT IN VARCHAR2,
```

```
PI_ISINSTONLY IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Business Area that you want to do check out.
If you are checking out the Business Area definition directly, enter values to identify the definition.

If you are checking out a Business Area definition through an instance of it, enter values to identify the instance.

The following attributes are required:
COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.
- **PI_COMMENT** Enter the reason you are checking out the Business Area.
- **PI_ISINSTONLY** (Mandatory) Enter \$YESNO\$NO.

Undo a Business Area Checkout

Use this API to undo the checkout of a Business Area definition, discarding any changes that have been made.

Name

CDR_PUB_DF_BUSINESSAREA.UncheckOutBusiArea

Signature

```
PROCEDURE UNCHECKOUTBUSIAREA(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_BASEOBJECT IN OUT CDR_BASE_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PIO_BASEOBJECT (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Business Area whose checkout you want to undo.

The following attributes are required:
COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

Check In a Business Area

Use this API to check in a Business Area definition.

Name

CDR_PUB_DF_BUSINESSAREA.CheckInBusiAreaDefinition

Signature

```
PROCEDURE CHECKINBUSIAREADEFINITION(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_BASEOBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PI_COMMENT IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Business Area that you want to check in.
The following attributes are required:
COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.
- **PI_COMMENT** (Optional) Enter the reason you are checking in the Business Area.

Remove a Business Area

Use this API to remove one or more Business Area definitions or instances.

Name

CDR_PUB_DF_BUSINESSAREA.RemoveBusiArea

Signature

```
PROCEDURE REMOVEBUSIAREA(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_CDRBASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

- **PIO_CDRBASEOBJCOLL** (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES.

For each Business Area that you want to remove, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.

The following attributes are required:

COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

Create and Modify Business Area Hierarchies

This is a public interface for all Business Area hierarchy-related operations, including creating, modifying, and removing Business Area hierarchies and hierarchy columns.

This section contains the following topics:

- [Create a Business Area Hierarchy](#)
- [Modify a Hierarchy and a Hierarchy Column](#)
- [Reorder a Hierarchy Column](#)
- [Remove a Hierarchy Column](#)
- [Remove a Business Area Hierarchy](#)

Create a Business Area Hierarchy

Use this API to create a hierarchy in a Business Area. To define the hierarchy's columns, use `ModifyBusAreaHierAndHierCol`.

Name

`CDR_PUB_DF_BUSINESSAREA_HIER.CreateBusinessAreaHier`

Signature

```
PROCEDURE CREATEBUSINESSAREAHIER(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PIO_SOURCECDRNAMING (Mandatory) This is a parameter of table type `CDR_NAMING_VERSION_OBJ_TYPE`.

Enter values for the new hierarchy. Use the `NAMESPACE` attributes to identify the Business Area in which you want to create the hierarchy.

The following attributes are required:

`OBJECT_TYPE_RC`, `NAME`, `NAMESPACE_OBJ_ID`, `NAMESPACE_OBJ_VER`, `OBJECT_SUBTYPE_ID`. For `OBJECT_TYPE_RC` enter `$OBJTYPES$BUSAREAHIER`.

Modify a Hierarchy and a Hierarchy Column

Use this API to modify Business Area hierarchies and hierarchy columns. You can change name and description, add columns, and change their Group With Previous setting. Use the remove columns API to remove columns.

Name

CDR_PUB_DF_BUSINESSAREA_HIER.ModifyBusAreaHierAndHierCol

Signature

```
PROCEDURE MODIFYBUSAREAHIERANDHIERCOL (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_NAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PI_BUS_HIERCOLUMNS_COLL IN OUT CDR_BUSAREA_HIER_COLS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Business Area Hierarchy that you want to modify and enter new values for the attributes you want to modify. You can modify only the Name and Description. All attributes are required.
- **PI_BUS_HIERCOLUMNS_COLL** (Mandatory) This is a collection of CDR_BUSAREA_HIER_COLS_OBJ_TYPE. Initialize a CDR_BUSAREA_HIER_COLS_OBJ_TYPE for each Column in their position order with the values you want to change, and then extend the collection. All attributes are required.

Reorder a Hierarchy Column

Use this API to reorder the Columns of a Business Area Hierarchy.



Note:

The API enforces validation rules for Column sequence.

Name

CDR_PUB_DF_BUSINESSAREA_HIER.ReorderHierCols

Signature

```
PROCEDURE REORDERHIERCOLS (
  P_API_VERSION IN NUMBER,
```

```

P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT VARCHAR2,
X_MSG_COUNT OUT NUMBER,
X_MSG_DATA OUT VARCHAR2,
PIO_BUS_HIERCOLUMNS_COLL IN OUT CDR_BUSAREA_HIER_COLS_COLL
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PIO_BUS_HIERCOLUMNS_COLL (Mandatory) This is a collection of CDR_BUSAREA_HIER_COLS_OBJ_TYPES. For each Column, initialize a CDR_BUSAREA_HIER_COLS_OBJ_TYPE, providing the new value for POSITION NUMBER relative to the other Columns, and then extend the collection. You must initialize all existing Columns.

The following attributes are required:

COMPANY_ID,HIER_OBJ_ID,HIER_OBJ_VER,TD_COMPANY_ID,TD_OBJ_ID,TD_COL_COMPANY_ID,TD_COL_OBJ_ID,POSITION,GROUP_WITH_PREVIOUS_RC.

Remove a Hierarchy Column

Use this API to remove Business Area Hierarchy Columns.



Note:

You cannot remove a Column that is currently part of a Join. If you remove a Column, and if the next Column's Group By Previous setting is Yes, then that setting is changed to No.

Name

CDR_PUB_DF_BUSINESSAREA_HIER.RemoveHierColumns

Signature

```

PROCEDURE REMOVEHIERCOLUMNS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_BUS_HIERCOLUMNS_COLL IN OUT CDR_BUSAREA_HIER_COLS_COLL
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_BUS_HIERCOLUMNS_COLL (Mandatory) This is a collection of CDR_BUSAREA_HIER_COLS_OBJ_TYPES. For each Column that you want to remove, initialize a CDR_BUSAREA_HIER_COLS_OBJ_TYPE and then extend the collection.

The following attributes are required:

COMPANY_ID,HIER_OBJ_ID,HIER_OBJ_VER,TD_COMPANY_ID,TD_OBJ_ID,TD_COL_COMPANY_ID,TD_COL_OBJ_ID,POSITION,GROUP_WITH_PREVIOUS_RC.

Remove a Business Area Hierarchy

Use this API to remove one or more Business Area Hierarchies, including all their Columns.

Name

CDR_PUB_DF_BUSINESSAREA_HIER.RemoveHiers

Signature

```
PROCEDURE REMOVEHIERS (
    P_API_VERSION IN NUMBER,
    P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
    P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
    P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
    X_RETURN_STATUS OUT VARCHAR2,
    X_MSG_COUNT OUT NUMBER,
    X_MSG_DATA OUT VARCHAR2,
    PI_BASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_BASEOBJCOLL (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES. For each Hierarchy that you want to remove, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.

The following attributes are required:

COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

Create and Modify Business Area Joins

This is a public interface for Business Area Join-related operations, including creating, modifying, and removing Business Area Joins and Join Columns.

This section contains the following topics:

- [Create a Join](#)
- [Modify a Join and a Join Column](#)
- [Remove a Join Column](#)
- [Remove a Join](#)

Create a Join

Use this API to create a Business Area Join.

Name

CDR_PUB_DF_BUSINESSAREA_JOIN.CreateBusinessAreaJoin

Signature

```
PROCEDURE CREATEBUSINESSAREAJOIN (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PI_BUSAREAJOINSOBJTYPE IN CDR_BUSAREA_JOINS_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values for the Join that you want to create. Use the NAMESPACE attributes to identify the Business Area in which you want to create the Join.
The following attributes are required:
OBJECT_TYPE_RC, NAME, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_S
UBTYPE_ID. For OBJECT_TYPE_RC enter \$OBJTYPES\$JOIN.
- **PI_BUSAREAJOINSOBJTYPE** (Mandatory) This is a parameter of table type CDR_BUSAREA_JOINS_OBJ_TYPE specific to Joins. Enter values for the Join that you want to create.
The following attributes are required:
TD_COMPANY_ID, TD_OBJ_ID, FK_TD_COMPANY_ID, FK_TD_OBJ_ID, TD_OUTERJOIN
_RC, FK_TD_OUTERJOIN_RC.

For TD_OUTERJOIN_RC and FK_TD_OUTERJOIN_RC, enter \$YESNO\$NO to define an inner join on the side of the corresponding Table Descriptor, or \$YESNO\$YES to define an outer join. Be sure to define an outer join on only one side, if any.

Modify a Join and a Join Column

Use this API to modify Business Area Joins and Join Columns. You can change the name and description of the Join and change either side to an inner or outer join (but be careful not to make both sides into outer joins). You can add Join Columns and pair them with a different Column from the other Table Descriptor.



Note:

Do not change the operator. EQUAL TO is the only operator currently supported.

Name

CDR_PUB_DF_BUSINESSAREA_JOIN.ModifyBusAreaJoinAndJoinCol

Signature

```
PROCEDURE MODIFYBUSAREAJOINANDJOINCOL (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
```

```

P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT VARCHAR2,
X_MSG_COUNT OUT NUMBER,
X_MSG_DATA OUT VARCHAR2,
PIO_NAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
PI_BUSINESS_JOIN IN OUT CDR_BUSAREA_JOINS_OBJ_TYPE,
PI_BUS_JOINCOLUMNS_COLL IN OUT CDR_BUSAREA_JOIN_COLS_COLL
);

```

Parameters

This API has standard parameters (see "[Standard Parameters](#)") and the following parameters:

- **PIO_NAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Join that you want to modify and for the attributes you want to change.
The following attributes are required:
COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.
- **PI_BUSINESS_JOIN** (Mandatory) This is a parameter of table type CDR_BUSAREA_JOINS_OBJ_TYPE specific to Joins. Enter values to identify the Join that you want to modify and the values you want to modify. All attributes are required.
- **PI_BUS_JOINCOLUMNS_COLL** (Mandatory) This is a collection of CDR_BUSAREA_JOIN_COLS_TYPES. For each Join Column that you want to modify, initialize a CDR_BUSAREA_JOIN_COLS_TYPE and then extend the collection.
The following attributes are required:
COMPANY_ID,JOIN_OBJ_ID,JOIN_OBJ_VER,TD_COL_COMPANY_ID,TD_COL_OBJ_ID,FK_TD_COL_COMPANY_ID,FK_TD_COL_OBJ_ID,POSITION. You can change the joined columns but you cannot modify the operator, which is always Equal To.

Remove a Join Column

Use this API to remove one or more Columns from a Join.

Name

CDR_PUB_DF_BUSINESSAREA_JOIN.RemoveJoinColumns

Signature

```

PROCEDURE REMOVEJOINCOLUMNS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_BUS_JOINCOLUMNS_COLL IN OUT CDR_BUSAREA_JOIN_COLS_COLL
);

```

Parameters

This API has standard parameters (see "[Standard Parameters](#)") and the following parameter:

- **PIO_BUS_JOINCOLUMNS_COLL** (Mandatory) This is a collection of CDR_BUSAREA_JOIN_COLS_TYPES. For each Join Column that you want to remove, initialize a CDR_BUSAREA_JOIN_COLS_TYPE and then extend the collection.

The following attributes are required:

COMPANY_ID,JOIN_OBJ_ID,JOIN_OBJ_VER,TD_COL_COMPANY_ID,TD_COL_OBJ_ID,FK_TD_COL_COMPANY_ID,FK_TD_COL_OBJ_ID,POSITION.

Remove a Join

Use this API to remove one or more Joins, with all their Columns, from a Business Area.

Name

CDR_PUB_DF_BUSINESSAREA_JOIN.RemoveJoins

Signature

```
PROCEDURE REMOVEJOINS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_BASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_BASEOBJCOLL (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES.

For each Join that you want to remove from the Business Area, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.

The following attributes are required:

COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

Public APIs and Naming Views for Generic Visualization Adapter (GVA)

This is a public interface for operations related to Generic Visualization Business Areas including initializing and resetting them.

For more information on integrating a data visualization tool, see *Oracle Life Sciences Data Management Workbench Data Visualization Integration Guide* (Document ID E87987-01) on My Oracle Support.

This section contains the following topics:

- [Initialize a Generic Visualization Business Area Instance](#)
- [Reset a Generic Visualization Business Area Instance](#)
- [Get Possible Blinding Types of a Business Area Instance](#)
- [Get Snapshot Labels Common to all Tables in a BA Instance for a Given Blinding AccessType](#)
- [Get Custom Listing Business Area ID](#)

- [Initialize Only Discrepancy View for Oracle DMW Business Area](#)

Initialize a Generic Visualization Business Area Instance

Use this API to initialize a business area instance with a given currency and blinding access type to determine which data is displayed. The visualization tool must run this API each time:

- A user logs in.
- The user changes the currency or blinding setting.
- A user selects a business area to view. Users can view multiple business areas in a single session as long as the user selects compatible blinding settings for all business areas. If the user selects a blinding access type for a business area that is incompatible with the blinding access types selected for other business areas in the same session, the API errors out with the message, "There is a change in reading dummy data to blinded data or vice-versa. Please reset access to all business areas using resetBAAccess api and try again." See [Reset a Generic Visualization Business Area Instance](#).

If the currency and the blinding access values are not set by the user, the API uses the default values, which are to show current and nonblinded data.



Tip:

There are two versions of API CDR_PUB_API_GVA.setInitializeBa with the same name. One allows entering a timestamp for the currency, while the other one accepts either the value `CURRENT` or a snapshot label.

Signature for Version 1

```
PROCEDURE SETINITIALIZEBA(
PI_COMPANYID IN CDR_NAMINGS.COMPANY_ID%TYPE,
PI_OBJID      IN CDR_NAMINGS.OBJ_ID%TYPE,
PI_OBJVER     IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE,
PI_VCURRENCY  IN VARCHAR2,
PI_VBLINDINGACCESSTYPE IN VARCHAR2,
X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT    OUT NOCOPY NUMBER,
X_MSG_DATA     OUT NOCOPY VARCHAR2)
```

Signature for Version 2

```
PROCEDURE SETINITIALIZEBA(
PI_COMPANYID IN CDR_NAMINGS.COMPANY_ID%TYPE,
PI_OBJID      IN CDR_NAMINGS.OBJ_ID%TYPE,
PI_OBJVER     IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE,
PI_REFRESHTS  IN DATE,
PI_VBLINDINGACCESSTYPE IN VARCHAR2,
X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT    OUT NOCOPY NUMBER,
X_MSG_DATA     OUT NOCOPY VARCHAR2)
```

Parameters

PI_COMPANYID. Enter the business area instance's company ID.

PI_OBJID. Enter the business area instance's object ID.

PI_OBJVER. Enter the business area instance's object version.

PI_VCURRENCY. Enter `Current` or a snapshot label common to all Table instances. See [Get Snapshot Labels Common to all Tables in a BA Instance for a Given Blinding AccessType](#).

OR

PI_DREFRESHTS Timestamp of the data currency required. Use any valid Oracle date or datetime format. The system displays data that was current at the date and time specified. For example, if data was loaded for the first time at 1:00 pm and then again at 2:00 pm:

- If the user specifies a timestamp of 1:30 pm, the visualization displays data loaded at 12:00.
- If the user specifies a timestamp of 12:00 pm, the visualization displays no data.
- If the user specifies a timestamp of 4:00 pm, the visualization displays data loaded at 2:00 pm.

PI_VBLINDINGACCESSTYPE. Enter the blinding access type. The allowed values are: `NA/Dummy`, `Masked Data`, `Real (Unblinded)`, and `Real (BlindBreak)`. Note that there is no space between `Real` and the parentheses/brackets.

- **NA/Dummy:** The user sees dummy data for data blinded at the table level.
- **Masked Data:** The user sees masking values for data blinded at the column, row, or cell level.
- **Real (Unblinded):** The user sees real data in unblinded table instances. This option is available only if *all* the business area's table instances whose Blinding flag is set to Yes have a Blinding Status of Unblinded.
- **Real (Blind Break):** The user sees currently blinded data in blinded table instances.
- **Real (Unblinded) and Real (Blind Break)** can be specified together: The user sees unblinded data in business area instances where this option is available (all table instances that have their Blinding Flag set to Yes must have a Blinding Status of Unblinded) and currently blinded data in other business area instances in the same session.



Tip:

There is no space between `Real` and the parentheses/brackets.

Reset a Generic Visualization Business Area Instance

Use this API to clear all the initializations of Business Area schemas. It is equivalent to logging out and logging back in to the system. Use this API when you want to change blinding access type from blinded to unblinded or vice-versa.

Name

CDR_PUB_API_GVA.RESETBAACCESS

Get Possible Blinding Types of a Business Area Instance

Use this API to get the possible Blinding Access Types of a Business Area Instance, which is in turn based on the blinding statuses of underlying Business Area Table instances and the user's privileges.

Name

CDR_PUB_API_GVA.GetBAValidBlindingAccessTypes

Signature

```
FUNCTION GETBAVALIDBLINDINGACCESSTYPES (
    PI_COMPANYID IN CDR_NAMINGS.COMPANY_ID%TYPE,
    PI_OBJID      IN CDR_NAMINGS.OBJ_ID%TYPE,
    PI_OBJVER     IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE) RETURN BLINDINGACCESSTYPESCOLL
PIPELINED;
```

Return

A collection of the possible blinding access types. BLINDINGACCESSTYPESCOLL is TABLE TYPE OF VARCHAR2(30);

Parameters

This API has the following parameters:

PI_COMPANYID. Enter the Business Area Instance Company ID.

PI_OBJID. Enter the Business Area Instance Object ID.

PI_OBJVER. Enter the Business Area Instance Object Version.

BLINDINGACCESSTYPESCOLL. This is the list of possible blinding access types.

Get Snapshot Labels Common to all Tables in a BA Instance for a Given Blinding AccessType

Use this API to get the snapshot labels common to all Tables within a Business Area Instance for a given blinding access type.

Name

CDR_PUB_API_GVA.GetSnapshotLabels

Signature

```
FUNCTION GETSNAPSHOTLABELS (
    PI_COMPANYID IN CDR_NAMINGS.COMPANY_ID%TYPE,
    PI_OBJID      IN CDR_NAMINGS.OBJ_ID%TYPE,
    PI_OBJVER     IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE,
    PI_VBLINDINGACCESSTYPE IN VARCHAR2) RETURN CURRENCYCOLL PIPELINED;
```

Return

A collection of the snapshot labels for a particular blinding access type in the Business Area instance common to all Tables within a Business Area Instance. CURRENCYCOLL is TABLE TYPE OF VARCHAR2(200);

Parameters

This API has the following parameters.

PI_COMPANYID. Enter the Business Area Instance Company ID.

PI_OBJID. Enter the Business Area Instance Object ID.

PI_OBJVER. Enter the Business Area Instance Object Version.

PI_VBLINDINGACCESSTYPE. Enter the Blinding Access Type.

Get Custom Listing Business Area ID



Note:

This API is not supported in Oracle DMW 3.3 release.

When a user logs into a visualization tool, the visualization tool must call an API to initialize the primary data model schema and, if the user wants to see custom listings through the tool, the schema for custom listings. The initialization API requires the business area instance ID, which is not available to a user in DMW.

Use this API to fetch the ID of the business area instance that contains all the custom listings defined in the model.

Signature

```
FUNCTION getCustomListingBA(
pi_nDataModelId IN NUMBER,
pi_vContext IN VARCHAR2)
RETURN NUMBER;
```

Parameters

pi_nDataModelId Enter the ID of the data model.

pi_vContext Enter the life cycle context value. The allowed values are: \$LIFECYCLE\$DEV, \$LIFECYCLE\$PROD, or \$LIFECYCLE\$QC.

Initialize Only Discrepancy View for Oracle DMW Business Area

Use this API to initialize only the discrepancy view for the Oracle DMW business area. Users will not be able to access the source table when they use this API.

Signature

```
PROCEDURE setDiscrepancyView(pi_objId          IN NUMBER,
pi_objVer          IN NUMBER,
pi_vBlindingAccessType IN VARCHAR2,
x_return_status    OUT NOCOPY VARCHAR2,
x_msg_count        OUT NOCOPY    NUMBER,
x_msg_data         OUT NOCOPY    VARCHAR2 );
```

Parameters

pi_objId Enter the Business Area Instance Object ID.

pi_objVer Enter the Business Area Instance Object Version.

pi_vBlindingAccessType Enter the blinding access type.

x_return_status Enter the return status.

x_msg_count Enter the message count.

x_msg_data Enter the actual message.

6

Data Marts

This is a public interface for creating, modifying, and removing Data Marts.

This chapter contains this section:

- [Define and Modify Data Marts](#)

Define and Modify Data Marts

This section contains the following topics:

- [Create a Data Mart](#)
- [Check In a DataMart Definition](#)
- [Modify a Data Mart](#)
- [Check Out a Data Mart](#)
- [Remove a Data Mart](#)

Create a Data Mart

Use this API to create a new Data Mart definition, a new instance of an existing Data Mart definition, or a new definition and an instance of it.

Name

CDR_PUB_DF_DATAMART.CreateDataMart

Signature

```
PROCEDURE CREATEDATAMART(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  X_RETURN_STATUS OUT VARCHAR2,  
  X_MSG_COUNT OUT NUMBER,  
  X_MSG_DATA OUT VARCHAR2,  
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,  
  PI_CDRDATAMARTOBJTYPE IN CDR_DATA_MART_OBJ_TYPE,  
  PI_CREATEOBJECT IN VARCHAR2,  
  PI_INSTANCE_SUBTYPE_ID IN CDR_NAMINGS.OBJECT_SUBTYPE_ID%TYPE,  
  PI_DEFCCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL,  
  PI_INSTCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes.

If you are only creating a new definition or a new definition and an instance of it, enter values for the new definition. If you are creating a definition enter \$OBJTYPES\$DATAMART for OBJECT_TYPE_RC. Enter NULL if you are creating a new definition and an instance of it.

If you are creating an instance of an existing definition, enter values to identify the definition. If you are creating an instance of an existing definition enter \$OBJTYPES\$DATAMARTREF for OBJECT_TYPE_RC.

- **PI_CDRDATAMARTOBJTYPE** (Optional) This is a parameter of table type CDR_DATA_MART_OBJ_TYPE that contains object attributes specific to Data Marts. If you are creating a new definition, enter values for the new Data Mart. The following attributes are required: COMPANY_ID, ADAPTER_COMPANY_ID, ADAPTER_OBJ_ID, ADAPTER_OBJ_VER.

If you are creating an instance of an existing Data Mart, do not enter any values here.
- **PI_CREATEOBJECT** (Mandatory) Enter DEFN to create a definition only; INST to create an instance of an existing definition; or BOTH to create a new definition and an instance of it.
- **PI_INSTANCE_SUBTYPE_ID** (Optional) If you are creating a new instance, enter the ID for the subtype you want to give the instance. If you are creating a definition only, do not enter a value for this parameter.
- **PI_DEFCLASSIFICATIONCOLL** (Optional) By default the new definition is classified according to the subtype you assigned it in the CDR_NAMING_VERSION_OBJ_TYPE. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID.
If you want the definition to inherit its classifications for a particular level from its parent, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are not relevant to Data Marts. Do not enter any values for them. If you are not creating a new definition, do not enter values here.
- **PI_INSTCLASSIFICATIONCOLL** The definition is classified according to the subtype you assigned it in the PI_INSTANCE_SUBTYPE_ID. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID. If you want the instance to inherit its classifications for a particular level from its parent Work Area, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero). If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are not relevant to Data Marts. Do not enter any values for them. If you are not creating a new instance, do not enter values here.

Check In a DataMart Definition

Use this API to check in a Data Mart definition.

Name

CDR_PUB_DF_DATAMART.CheckInDataMartDefinition

Signature

```
PROCEDURE CHECKINDATAMARTDEFINITION(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_BASEOBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PI_COMMENT IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Data Mart definition that you want to check in. The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.
- **PI_COMMENT** (Optional) Enter the reason you are checking in the Data Mart.

Modify a Data Mart

Use this API to modify a Data Mart definition or instance. You can modify the name and description. If you are modifying an instance object, you can also change the 3 REF attribute values to select a different source definition.

Note: If you are modifying a definition, you must first check it out.

Name

CDR_PUB_DF_DATAMART.ModifyDataMart

Signature

```
PROCEDURE MODIFYDATAMART(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_CDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_CDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Data Mart and enter new values for the attributes you want to modify. You can change the name or description for either a definition or instance. For an instance you can also change to a different underlying source

definition by entering values for the new definition in the three REF attributes. All attributes are required.

NOTE: Use separate APIs for modifying the validation status and the version label: CDR_PUB_VL_VALIDATION. UpdateValStatus and CDR_PUB_DF_NAMING. UpdateVersionLabel.

Check Out a Data Mart

Use this API to check out a Data Mart definition, either directly or through an instance of it.

Name

CDR_PUB_DF_DATAMART.CheckOutDataMart

Signature

```
PROCEDURE CHECKOUTDATAMART(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_BASEOBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PI_COMMENT IN VARCHAR2,
  PI_ISINSTONLY IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Data Mart that you want to do check out. If you are checking out the Data Mart definition directly, enter values to identify the definition. If you are checking out a Data Mart definition through an instance of it, enter values to identify the instance.

The following attributes are required:

COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.

The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER. For OBJECT_TYPE_RC enter \$OBJTYPES\$WORKAREA. By default, new Work Areas receive a Usage Intent value of Development.

- **PI_COMMENT** (Optional) Enter the reason you are checking out the Data Mart.
- **PI_ISINSTONLY** (Mandatory) Enter \$YESNO\$NO.

Remove a Data Mart

Use this API to remove one or more Data Mart definitions or instances.

Name

CDR_PUB_DF_DATAMART.RemoveDataMart

Signature

```
PROCEDURE REMOVEDATAMART(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  X_RETURN_STATUS OUT VARCHAR2,  
  X_MSG_COUNT OUT NUMBER,  
  X_MSG_DATA OUT VARCHAR2,  
  PIO_CDRBASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PIO_CDRBASEOBJCOLL (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES. For each Data Mart that you want to remove, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.

The following attributes are required:

COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

7

Domains

This is a public interface for Domain-related operations, including creating, modifying, and removing Domains. It also includes functions for copying and moving objects into Domains.

This chapter contains this section:

- [Define and Modify Domains](#)

Define and Modify Domains

This section contains the following topics:

- [Create a Domain](#)
- [Modify a Domain](#)
- [Copy a Domain](#)
- [Move Objects into a Domain](#)
- [Copy Objects into a Domain](#)
- [Check in Objects and Copy them into a Different Domain](#)
- [Remove a Domain](#)

Create a Domain

Use this API to create a new Domain.

Name

CDR_PUB_DF_DOMAIN.CreateDomain

Signature

```
PROCEDURE CREATEDOMAIN(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  X_RETURN_STATUS OUT VARCHAR2,  
  X_MSG_COUNT OUT NUMBER,  
  X_MSG_DATA OUT VARCHAR2,  
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,  
  PO_DEFLCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. For OBJECT_TYPE_RC enter \$OBJTYPES\$LIBDOMAIN.

- **PO_DEFCLASSIFICATIONCOLL** (Optional) By default the new Domain is classified according to the subtype you assigned it in the CDR_NAMING_VERSION_OBJ_TYPE. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID. I

If you want the definition to inherit its classifications for a particular level from its parent, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are not relevant to Domains. Do not enter any values for them.

Modify a Domain

Use this API to modify a Domain.

Name

CDR_PUB_DF_DOMAIN.ModifyDomain

Signature

```
PROCEDURE MODIFYDOMAIN(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PIO_SOURCECDRNAMING (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Domain and enter new values for the attributes you want to modify. The COMPANY_ID, OBJ_ID and OBJ_VER of the domain to be modified should be initialized.



Note:

Use separate APIs for modifying the validation status and the version label: CDR_PUB_VL_VALIDATION.UPDATEVALSTATUS and CDR_PUB_DF_NAMING.UPDATEVERSIONLABEL.

Copy a Domain

Use this API to make a copy of a Domain.

Name

CDR_PUB_DF_DOMAIN.CopyDomain

Signature

```
PROCEDURE COPYDOMAIN(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_CDRBASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PI_CDRBASEOBJCOLL (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES. For each Domain that you want to copy, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.

The following attributes are required:

COMPANY_ID,OBJ_ID,OBJ_VER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER,
OBJECT_VERSION_NUMBER.

Move Objects into a Domain

Use this API to move subdomains, Application Areas, and object definitions from one Domain or Application Area, into another Domain.

Name

CDR_PUB_DF_DOMAIN.MoveObjectsIntoDomain

Signature

```
PROCEDURE MOVEOBJECTSINTODOMAIN(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_CDRBASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL,
  PI_CDRTARGETCONTAINEROBJECT IN OUT CDR_BASE_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_CDRBASEOBJCOLL** (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES. For each object that you want to move, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.

The following attributes are required:

COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,
NAMESPACE_OBJ_VER

- **PI_CDRTARGETCONTAINEROBJECT** (Mandatory) This is a parameter of CDR_BASE_OBJ_TYPE and contains basic naming details about the Domain into which you want move objects.

The following attributes are required: COMPANY_ID,OBJ_ID,OBJ_VER,
NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, and OBJECT_VERSION_NUMBER).

Copy Objects into a Domain

Use this API to copy objects into a Domain. You can copy subdomains, Application Areas, and object definitions from other Domains or Application Areas.

Name

CDR_PUB_DF_DOMAIN.CopyObjectsIntoDomain

Signature

```
PROCEDURE COPYOBJECTSINTODOMAIN(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_CDRBASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL,
  PI_CDRTARGETCONTAINEROBJECT IN OUT CDR_BASE_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_CDRBASEOBJCOLL** (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES. For each object that you want to copy, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.
The following attributes are required:
COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,
NAMESPACE_OBJ_VER.
- **PI_CDRTARGETCONTAINEROBJECT** (Mandatory) This is a parameter of CDR_BASE_OBJ_TYPE and contains basic naming details about the Domain into which you want copy objects.
The following attributes are required: COMPANY_ID, OBJ_ID,OBJ_VER,
NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, and OBJECT_VERSION_NUMBER).

Check in Objects and Copy them into a Different Domain

Use this overloaded API to copy objects into a Domain and check them in if they are checked out, before copying.

Name

CDR_PUB_DF_DOMAIN.CopyObjectsIntoDomain

Signature

```
PROCEDURE COPYOBJECTSINTODOMAIN(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_CDRBASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL,
  PI_CDRTARGETCONTAINEROBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PI_CHECKINFLAG IN VARCHAR
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_CDRBASEOBJCOLL** (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES. For each object that you want to copy, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.
The following attributes are required:
COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.
- **PI_CDRTARGETCONTAINEROBJECT** (Mandatory) This is a parameter of CDR_BASE_OBJ_TYPE and contains basic naming details about the Domain into which you want copy objects.
The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, and OBJECT_VERSION_NUMBER).
- **PI_CHECKINFLAG** (Mandatory) Enter \$YESNO\$YES if you want to check in the copied objects, if they are checked out, and \$YESNO\$NO if you do not want to check in the copied objects.

Remove a Domain

Use this API to delete a Domain.

Name

CDR_PUB_DF_DOMAIN.RemoveDomain

Signature

```
PROCEDURE REMOVEDOMAIN(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_DOMAIN IN OUT CDR_BASE_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PIO_DOMAIN Mandatory) This is a parameter of CDR_BASE_OBJ_TYPE and contains basic naming details about the Domain you want to delete.

The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, and OBJECT_VERSION_NUMBER).

8

Load Sets

This is a public interface for Load Set-related operations, including creating, modifying, and removing Load Sets. It also includes APIs for checking Load Sets in and out, undoing a Load Set checkout, and computing the status of a Load Set.

This chapter contains this section:

- [Define and Modify Load Sets](#)

Define and Modify Load Sets

This section contains the following topics:

- [Create a Load Set](#)
- [Check Out a Load Set](#)
- [Modify a Load Set](#)
- [Check In a Load Set Definition](#)
- [Undo Check Out for a Load Set Definition](#)
- [Remove a Load Set](#)
- [Synchronize Table Descriptors in a Load Set](#)

Create a Load Set

Use this API to create a Load Set definition, Load Set instance or both.

Name

CDR_PUB_DF_LOADSET.CreateLoadSet

Signature

```
PROCEDURE CREATELOADSET(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  X_RETURN_STATUS OUT VARCHAR2,  
  X_MSG_COUNT OUT NUMBER,  
  X_MSG_DATA OUT VARCHAR2,  
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,  
  PI_CDRLOADSETOBJTYPE IN CDR_LOAD_SET_OBJ_TYPE,  
  PI_CREATEOBJECT IN VARCHAR2,  
  PI_INSTANCE_SUBTYPE_ID IN CDR_NAMINGS.OBJECT_SUBTYPE_ID%TYPE,  
  PI_DEFCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL,  
  PI_INSTCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SOURCECDRNAMING** :(Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. If you are creating a new definition only or a new definition and an instance of it, enter values for the new definition. If you are creating an instance of an existing definition, enter values to identify the existing definition.

For OBJECT_TYPE_RC enter \$OBJTYPES\$LOADSET if you are creating a definition only; \$OBJTYPES\$LOADSETREF if you are creating an instance of an existing definition; and NULL if you are creating a new definition and an instance of it.

- **PI_CDRLOADSETOBJTYPE** (Mandatory) This is a parameter of table type CDR_LOAD_SET_OBJ_TYPE that contains object attributes specific to Load Sets. Enter values for the Load Set that you want to create.
The following attributes are required: COMPANY_ID, ADAPTER_COMPANY_ID, ADAPTER_OBJ_ID, ADAPTER_OBJ_VER.
- **PI_CREATEOBJECT** (Mandatory) Enter DEFN to create a definition only; INST to create an instance of an existing definition; or BOTH to create a definition and an instance of it
- **PI_INSTANCE_SUBTYPE_ID** (Optional) If you are creating a new instance, enter the subtype ID that you want to give the instance.
If you are creating a definition only, do not enter a value for this parameter.
- **PI_DEFCLASSIFICATIONCOLL** (Optional) By default, the new definition is classified according to the subtype you assigned it in the CDR_NAMING_VERSION_OBJ_TYPE. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID.

If you want the definition to inherit its classifications for a particular level from its parent, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are not relevant to Load Sets. Do not enter any values for them.

If you are not creating a new definition, do not enter values here.

- **PI_INSTCLASSIFICATIONCOLL** PI_INSTANCE_SUBTYPE_ID. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID.
If you want the instance to inherit its classifications for a particular level from its parent Work Area, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are not relevant to Load Sets. Do not enter any values for them.

If you are not creating a new instance, do not enter values here.

Check Out a Load Set

Use this API to check out a Load Set definition or definition and instance.

Name

CDR_PUB_DF_LOADSET.CheckOutLoadSet

Signature

```
PROCEDURE CHECKOUTLOADSET (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_BASEOBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PI_COMMENT IN VARCHAR2,
  PI_ISINSTONLY IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. You can enter values to identify either the Load Set definition or an instance of it:
 - Pass the Load Set definition details if you want to check out and subsequently modify only the definition.
 - Pass the details of an instance of the Load Set definition if you want the instance to point to the new version of the Load Set definition.

The following attributes are required:

COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.

To get the OBJECT_VERSION_NUMBER, enter the following query: select Max(OBJECT_VERSION_NUMBER) from cdr_vl_val_docs_v where OBJ_ID = <objid> and OBJ_VER = <objver> and DOC_STATUS_RC ='\$VALINFOSTATUS\$ACTIVE';

NAMESPACE_OBJ_ID. If you are entering information about the Load Set definition, enter the object ID of its containing Application Area. If you are entering information about the Load Set instance, enter the object ID of its containing Work Area.

NAMESPACE_OBJ_VER. If you are entering information about the Load Set, definition, enter the object version number of its containing Application Area. If you are entering information about the Load Set instance, enter the object version number of its containing Work Area.

- **PI_COMMENT** (Optional) Enter the reason you are checking out the Load Set.
- **PI_ISINSTONLY** Enter \$YESNO\$NO if you are checking out only the definition. Enter \$YESNO\$YES if you are checking out the definition through its instance.

Modify a Load Set

Use this API to modify a Load Set definition or instance. You can change the name, description, or version label.

**Note:**

If you are modifying a definition, you must first check it out.

Name

CDR_PUB_DF_LOADSET.ModifyLoadSet

Signature

```
PROCEDURE MODIFYLOADSET(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_CDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PIO_CDRNAMING (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Load Set and enter new values for the attributes you want to modify. All attributes are required.

Check In a Load Set Definition

Use this API to check in a Load Set definition.

Name

CDR_PUB_DF_LOADSET.CheckInLoadSetDefinition

Signature

```
PROCEDURE CHECKINLOADSETDEFINITION(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_BASEOBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PI_COMMENT IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Load Set definition that you want to check in.

The following attributes are required:

COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,
NAMESPACE_OBJ_VER.

- **PI_COMMENT** (Optional) Enter the reason for checking in the Load Set.

Undo Check Out for a Load Set Definition

Use this API to undo a check out for a Load Set Definition.

Name

CDR_PUB_DF_LOADSET.UndoCheckOutLoadSet

Signature

```
PROCEDURE UNDOCHECKOUTLOADSET(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT NOCOPY VARCHAR2,
  X_MSG_COUNT OUT NOCOPY NUMBER,
  X_MSG_DATA OUT NOCOPY VARCHAR2,
  PIO_BASEOBJECT IN OUT NOCOPY CDR_BASE_OBJ_TYPE,
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **P_COMMIT** (Optional) Accept the default value (FND_API.G_FALSE) to ensure that this individual API does not commit upon completion. Enter FND_API.G_TRUE to override the default behavior.
- **P_VALIDATION_LEVEL** (Optional) Accept the default value to perform full validation. No other values are currently supported.
- **PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE that contains object attributes. Enter values to identify the Load Set definition that you want to undo check out.
The required attributes are: COMPANY_ID,
OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID,
NAMESPACE_OBJ_VER.

Remove a Load Set

Use this API to remove one or more Load Set definitions or instances.

Name

CDR_PUB_DF_LOADSET.RemoveLoadSet

Signature

```
PROCEDURE REMOVELOADSET(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
```

```

X_RETURN_STATUS OUT VARCHAR2,
X_MSG_COUNT OUT NUMBER,
X_MSG_DATA OUT VARCHAR2,
PIO_CDRBASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_CDRBASEOBJCOLL (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES.

For each Load Set definition or instance that you want to remove, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.

The following attributes are required:

COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.

Synchronize Table Descriptors in a Load Set

Use this API to synchronize all the existing table descriptors in a Load Set with the Table definition at the source. When you use this API, it performs different tasks according to the situation:

- If the API finds no changes to be synchronized, it displays a message indicating that there are no changes to the table descriptors.
- If the API finds changes to be synchronized and the Load Set definition is checked out, it synchronizes the changes and displays a message indicating that changes were identified and synchronized.
- If the API finds changes to be synchronized and the Load Set definition is checked in, then it checks out the Load Set, completes synchronization and leaves the Load Set checked out.

Table descriptors (and corresponding Table definitions) are checked out only if changes are detected. After synchronization is complete, the API returns a collection of Table descriptor objIDs and obj versions that were changed.

The API does not create a new table descriptor in the Load Set but only synchronizes the existing Table Descriptors. The updated Table Descriptor generates the same outcome as when columns are uploaded for a Table Descriptor.

Name

CDR_PUB_DF_LOADSET.SynchronizeTablesWithinLS

Signature

```

PROCEDURE SYNCHRONIZETABLESWITHINLS(
P_API_VERSION IN NUMBER,
P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER,
X_MSG_DATA OUT NOCOPY VARCHAR2,
PI_NLSDEFID IN NUMBER,
PI_NLSDEFID IN NUMBER,
PI_VFILENAME IN VARCHAR2,
PI_BFILEBLOB IN BLOB,

```

```
PO_TDESCLIST    OUT NOCOPY CDR_BASE_OBJ_COLL,  
PO_OUTMSG       OUT NOCOPY VARCHAR2 );
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

- **PARAM P_API_VERSION** (Mandatory). Enter the current version of the API you are calling. The API compares the version numbers of incoming calls to its current version number and returns an error if they are incompatible.
- **PARAM P_INIT_MSG_LIST** (Optional). Accept the default value (FND_API.G_FALSE) to ensure that this individual API does not initialize the message list upon completion. Pass FND_API.G_TRUE to override the default behavior.
- **PARAM P_COMMIT** (Optional). Accept the default value (FND_API.G_FALSE) to ensure that this individual API does not commit upon completion. Pass FND_API.G_TRUE to override the default behavior.
- **PARAM P_VALIDATION_LEVEL** (Optional). Accept the default value to perform full validation. No other values are currently supported.
- **PARAM X_RETURN_STATUS**. This output parameter returns the end status of the API: (S) Success, (E) Error or (U) Unexpected Error
- **PARAM X_MSG_COUNT**. This output parameter returns the count of error messages if the return status is other than Success.
- **PARAM X_MSG_DATA**. If the message count is 1, this output parameter returns the text of the error message. If there are more than one message, use `cdr_pub_msg_pub.get` to retrieve the messages.
- **PARAM PI_NLSDEFCOMPID**. Enter the Company Id.
- **PARAM PI_NLSDEFID**. Provide the Load Set Definition Id
- **PARAM PI_VFILENAME** (Optional). If the Load Set is a SAS or TEXT type, provide the file name.
For SAS—cport, xport, cpri, xpri and .sas*.dat files are allowed.
For TXT—zip and mdd files are allowed. The zip should only contain mdd files. The mdd file name should be the same as the Table Descriptor it needs to update. For other types, it can be sent as null.
- **PARAM PI_BFILEBLOB** (Optional). Provide the BLOB that holds the file content for SAS and TEXT Load Sets.
- **PARAM PO_TDESCLIST**. This list contains the table descriptors that were updated.
- **PARAM PO_OUTMSG**. Returns the error/confirmation messages.

9

Parameter Sets

This is a public interface for operations involving Parameter sets. These APIs provide procedures to create Parameter sets, modify Parameter set details, remove Parameter sets, check in, check out and uncheckout Parameter sets.

This chapter contains this section:

- [Create and Modify Parameter Sets](#)

Create and Modify Parameter Sets

This section contains the following topics:

- [Create a Parameter Set Definition](#)
- [Check Out a Parameter Set Definition](#)
- [Modify a Parameter Set Definition](#)
- [Modify a Parameter Set Detail](#)
- [Check In a Parameter Set Definition](#)
- [Remove a Parameter Set Definition](#)

Create a Parameter Set Definition

Use this API to create a new Parameter Set definition, a new instance of an existing Parameter Set definition, or a new definition and an instance of it.

Name

CDR_PUB_DF_PARAMETER_SET.CreateParameterSet

Signature

```
PROCEDURE CREATEPARAMETERSET (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PI_CDRPSOBJTYPE IN CDR_PARAM_SETS_OBJ_TYPE,
  PI_CREATEOBJECT IN VARCHAR2,
  PI_INSTANCE_SUBTYPE_ID IN CDR_NAMINGS.OBJECT_SUBTYPE_ID%TYPE,
  PI_DEFCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. If you are creating a new definition only or a new definition and an instance of it, enter values for the new definition.

If you are creating an instance of an existing definition, enter values to identify the definition. For OBJECT_TYPE_RC enter \$OBJTYPES\$PARAMSET if you are creating a definition only; \$OBJTYPES\$PARAMSETREF if you are creating an instance of an existing definition; and NULL if you are creating a new definition and an instance of it.
- **PI_CDRPSOBJTYPE** (Optional) This is a parameter of table type CDR_PARAM_SETS_OBJ_TYPE that contains object attributes specific to Parameter Sets.
If you are creating a new definition, enter values for the new Parameter Set.

The following attributes are required: COMPANY_ID, USAGE, PR_REF_ID, PR_REF_VER.

If you are creating an instance of an existing Parameter Set, do not enter any values here.
- **PI_CREATEOBJECT** (Mandatory) Enter DEFN to create a definition only; INST to create an instance of an existing definition; or BOTH to create a new definition and an instance of it.
- **PI_INSTANCE_SUBTYPE_ID** (Optional) If you are creating a new instance, enter the ID for the subtype you want to give the instance.
If you are creating a definition only, do not enter a value for this parameter.
- **PI_DEFCLASSIFICATIONCOLL** (Optional) By default, the new definition is classified according to the subtype you assigned it in the CDR_NAMING_VERSION_OBJ_TYPE. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID.

If you want the definition to inherit its classifications for a particular level from its parent, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are not relevant to Parameter Sets. Do not enter any values for them.

If you are not creating a new definition, do not enter values here.

Check Out a Parameter Set Definition

Use this API to check out a Parameter Set definition either directly or through an instance of it.

Name

CDR_PUB_DF_PARAMETER_SET.CheckOutParameterSet

Signature

```
PROCEDURE CHECKOUTPARAMETERSET (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_BASEOBJECT IN OUT CDR_BASE_OBJ_TYPE,
```

```

PI_COMMENT IN VARCHAR2,
PI_ISINSTONLY IN VARCHAR2
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Parameter Set that you want to check out.
If you are checking out the Parameter Set definition directly, enter values to identify the definition.

If you are checking out a Parameter Set definition through an instance of it, enter values to identify the instance.

The following attributes are required:
COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.
- **PI_COMMENT** (Optional) Enter the reason you are checking out the Parameter Set.
- **PI_ISINSTONLY** (Mandatory) Enter \$YESNO\$NO.

Modify a Parameter Set Definition

Use this API to modify the name or description of a Parameter Set definition.

Name

CDR_PUB_DF_PARAMETER_SET.ModifyParameterSetDefinition

Signature

```

PROCEDURE MODIFYPARAMETERSETDEFINITION(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_CDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

- **PIO_CDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Parameter Set and enter new values for the attributes you want to modify. You can change the name or description.



Note:

Use separate APIs for modifying the validation status and the version label: CDR_PUB_VL_VALIDATION.UPDATEVALSTATUS and CDR_PUB_DF_NAMING.UPDATEVERSIONLABEL. All attributes are required.

Modify a Parameter Set Detail

Use this API to modify Parameter Set details.

Name

CDR_PUB_DF_PARAMETER_SET.ModifyParameterSetDetails

Signature

```
PROCEDURE MODIFYPARAMETERSETDETAILS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_CDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_CDRNAMING Naming details of the parameter set object to be modified.

Check In a Parameter Set Definition

Use this API to check in a Parameter Set definition.

Name

CDR_PUB_DF_PARAMETER_SET.CheckInParameterSetDefinition

Signature

```
PROCEDURE CHECKINPARAMETERSETDEFINITION (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_BASEOBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PI_COMMENT IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Parameter Set definition that you want to check in.
The following attributes are required:
COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,
NAMESPACE_OBJ_VER.

- **PI_COMMENT** (Optional) Enter the reason you are checking in the Parameter Set.

Remove a Parameter Set Definition

Use this API to remove one or more Parameter Set definitions or instances.

Name

CDR_PUB_DF_PARAMETER_SET.RemoveParameterSet

Signature

```
PROCEDURE REMOVEPARAMETERSET(  
    P_API_VERSION IN NUMBER,  
    P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
    P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
    P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
    X_RETURN_STATUS OUT VARCHAR2,  
    X_MSG_COUNT OUT NUMBER,  
    X_MSG_DATA OUT VARCHAR2,  
    PIO_CDRBASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_CDRBASEOBJCOLL (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES.

For each Parameter Set that you want to remove, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.

The following attributes are required:

COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

Planned Outputs

This is a public interface for all Planned Output related functions including creating, modifying, removing, and copying Planned Outputs.

This chapter contains the following section:

- [Create and Modify Planned Outputs](#)

Create and Modify Planned Outputs

This section contains the following topics:

- [Create a Planned Output](#)
- [Get a New Position Number](#)
- [Get a Planned Output Object](#)
- [Modify a Planned Output](#)
- [Identify whether a SAS Object](#)
- [Remove a Planned Output Object](#)

Create a Planned Output

Use this API to create a Planned Output.

Name

CDR_PUB_DF_PLANNED_OUTPUT.CreatePlannedOutput

Signature

```
PROCEDURE CREATEPLANNEDOUTPUT (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PI_PLANNEDOUTPUTOBJTYPE IN OUT CDR_PLANNEDOUTPUT_OBJ_TYPE,
  PI_DEFCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of type CDR_NAMING_VERSIONS_OBJ_TYPE.

The following attributes are required: COMPANY_ID, OBJECT_TYPE_RC, NAME, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OWNING_LOCATION_RC, OBJECT_SUBTYPE_ID, DESCRIPTION, REF_COMPANY_ID, REF_OBJ_ID, REF_OBJ_VER.

For OBJECT_TYPE_RC enter \$OBJTYPES\$PLANNEDOUT.

- **PI_PLANNEDOUTPUTOBJTYPE** (Mandatory) This is a parameter of table type CDR_PLANNEDOUTPUT_OBJ_TYPE.
You need to pass the following attributes: COMPANY_ID, OBJ_ID, OBJ_VER, TITLE, POSITION, FILEREF, FILE_NAME, PRIMARY_FLAG_RC, ERROR_FILE_FLAG_RC, REQ_FILE_FLAG_RC.

For the POSITION attribute, use the GETNEWPOSITIONNUMBER API.

- **PI_DEFCLASSIFICATIONCOLL** (Optional) By default the new PLANNED OUTPUT is classified according to the subtype you assigned it in the CDR_NAMING_VERSION_OBJ_TYPE.
If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID.

If you want the definition to inherit its classifications for a particular level from its parent, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID.

If you want to use a Parameter to classify the actual output, use the PAR attributes to identify the Parameter. The Parameter's list of values must be based on a classification hierarchy level.

Get a New Position Number

Use this API to get a unique position number for a Planned Output within a parent object. This API is used from within the CREATEPLANNEDOUTPUT API, which is used to create a new Planned Output. You can also reorder Planned Outputs using this API.

Name

CDR_PUB_DF_PLANNED_OUTPUT.GetNewPositionNumber

Signature

```
FUNCTION GETNEWPOSITIONNUMBER(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PI_NCOMPANYID IN CDR_NAMINGS.COMPANY_ID%TYPE,
  PI_NOBJID IN CDR_NAMINGS.OBJ_ID%TYPE,
  PI_NOBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE
) RETURN NUMBER;
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NCOMPANYID** (Mandatory) Enter the COMPANY_ID of the parent object.
- **PI_NOBJID** (Mandatory) Enter the OBJ_ID of the parent object.

- **PI_NOBJVER** (Mandatory) Enter the OBJ_VER of the parent object.

Get a Planned Output Object

Use this API to retrieve a Planned Output object for an LSH object.

Name

CDR_PUB_DF_PLANNED_OUTPUT.GetPlannedOutputObject

Signature

```
FUNCTION GETPLANNEDOUTPUTOBJECT (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PI_NCOMPANYID IN CDR_NAMINGS.COMPANY_ID%TYPE,
  PI_NOBJID IN CDR_NAMINGS.OBJ_ID%TYPE,
  PI_NOBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE,
  PO_PLANNEDOUTPUT OUT CDR_PLANNEDOUTPUT_OBJ_TYPE
) RETURN BOOLEAN;
```

Return

Type BOOLEAN

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NCOMPANYID** (Mandatory) Enter your company ID. To get your company ID, use CDR_DF_PUB_DEF_CONSTANTS.CURRENT_COMPANY_ID.
- **PI_NOBJID** (Mandatory) Enter the OBJ_ID value of the object for which you want to retrieve the Planned Output object.
- **PI_NOBJVER** (Mandatory) Enter the OBJ_VER value of the object for which you want to retrieve the Planned Output's object.
- **PO_PLANNEDOUTPUT** This is the output parameter of the API returning the Planned Output Object.

Modify a Planned Output

Use this API to modify an existing Planned Output.

Name

CDR_PUB_DF_PLANNED_OUTPUT.ModifyPlannedOutput

Signature

```
PROCEDURE MODIFYPLANNEDOUTPUT (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
```

```

PI_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
PI_POUTOBJTYPE IN OUT CDR_PLANNEDOUTPUT_OBJ_TYPE
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Planned Output.
- **PI_POUTOBJTYPE** (Mandatory) This is a parameter of table CDR_PLANNEDOUTPUT_OBJ_TYPE that contains attributes specific to Planned Outputs. Enter values for the Planned Output and enter new values for the attributes you want to modify. You can change the name or description of a Planned Output.

Note:

Use separate APIs for modifying the validation status and the version label:
CDR_PUB_VL_VALIDATION.UPDATE_VAL STATUS and
CDR_PUB_DF_NAMING.UPDATEVERSIONLABEL.

Identify whether a SAS Object

Use this API to check if the parent object of the Planned Output is a SAS object. SAS objects are: SAS programs, SAS load Sets, SAS Tables.

Name

CDR_PUB_DF_PLANNED_OUTPUT.IsSASObject

Signature

```

FUNCTION ISSASOBJECT(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PI_NCOMPANYID IN CDR_NAMINGS.COMPANY_ID%TYPE,
  PI_NOBJID IN CDR_NAMINGS.OBJ_ID%TYPE,
  PI_NOBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE,
  PI_NSOBJTYPE IN CDR_NAMINGS.OBJECT_TYPE_RC%TYPE
) RETURN VARCHAR2;

```

Return

Type VARCHAR2 Description

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NCOMPANYID** (Mandatory) Enter your company ID.
To get your company ID, use CDR_PUB_DEF_FACTORY_UTILS.GetCompanyId.
- **PI_NOBJID** (Mandatory) Enter the object ID of the Planned Output's parent object.
- **PI_NOBJVER** (Mandatory) Enter the version number of the Planned Output's parent object.

- **PI_NSOBJTYPE** (Mandatory) Enter the OBJ_TYPE value for the Planned Output's parent object.

Remove a Planned Output Object

Use this API to delete one or more Planned Outputs.

Name

CDR_PUB_DF_PLANNED_OUTPUT.RemovePlannedOutput

Signature

```
PROCEDURE REMOVEPLANNEDOUTPUT (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_CDRBASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL,
  PI_GETLOCK IN VARCHAR := 'T'
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_CDRBASEOBJCOLL** (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES. For each Planned Output that you want to remove, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.

The following attributes are required:
COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,
NAMESPACE_OBJ_VER.
- **PI_GETLOCK** (Optional) Do not enter a value for this attribute. The default and only acceptable value is 'T'.

Programs

This is a public interface for Program-related functions, including creating, modifying, and removing Programs. It also includes functions for checking Programs in and out, and undoing a Program checkout.

This chapter contains the following section:

- [Create and Modify Programs](#)

Create and Modify Programs

This section contains the following topics:

**Note:**

See also [Install a Program](#).

- [Create a Program](#)
- [Copy Objects Into a Program](#)
- [Modify a Program](#)
- [Check In a Program Definition](#)
- [Check Out a Program Definition](#)
- [Remove a Program](#)
- [Create a Planned Output for a Log File](#)
- [Assign a Planned Output](#)
- [Modify a Manual Validation Flag Value](#)

Create a Program

Use this API to create a new Program definition, a new instance of an existing Program definition, or a new definition and an instance of it.

Name

CDR_PUB_DF_PROGRAM.CreateProgram

Signature

```
PROCEDURE CREATEPROGRAM(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  X_RETURN_STATUS OUT VARCHAR2,
```

```
X_MSG_COUNT OUT NUMBER,
X_MSG_DATA OUT VARCHAR2,
PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
PI_CDRPRGOBJTYPE IN CDR_PROGRAM_OBJ_TYPE,
PI_CREATEOBJECT IN VARCHAR2,
PI_INSTANCE_SUBTYPE_ID IN CDR_NAMINGS.OBJECT_SUBTYPE_ID%TYPE,
PI_DEFCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL,
PI_INSTCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type `CDR_NAMING_VERSIONS_OBJ_TYPE` that contains CDR Naming Version attributes. If you are creating a new definition only or a new definition and an instance of it, enter values for the new definition.

If you are creating an instance of an existing definition, enter values to identify the definition.

The required attributes are:
`OBJECT_TYPE_RC, NAME, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, NAMESPACE_START_OBJ_VER, NAMESPACE_END_OBJ_VER, OWNING_LOCATION_RC, OBJECT_SUBTYPE_ID`.

For `OBJECT_TYPE_RC` enter `$OBJTYPES$PROGRAM` if you are creating a definition only; `$OBJTYPES$PROGRAMINST` if you are creating an instance of an existing definition; and `NULL` if you are creating a new definition and an instance of it.
- PI_CDRPRGOBJTYPE** (Optional) This is a parameter of table type `CDR_DATA_MART_OBJ_TYPE` that contains object attributes specific to Programs. If you are creating a new definition, enter values for the new Program. The following attributes are required: `CDR_PROGRAM_OBJ_TYPE, TECH_TYPE_ID`.

If you are creating an instance of an existing Program, do not enter any values here.
- PI_CREATEOBJECT** (Mandatory) Enter `DEFN` to create a definition only; `INST` to create an instance of an existing definition; or `BOTH` to create a new definition and an instance of it.
- PI_INSTANCE_SUBTYPE_ID** (Optional) If you are creating a new instance, enter the ID for the subtype you want to give the instance.
If you are creating a definition only, do not enter a value for this parameter. Definition and Instance are to be created in the same call.
- PI_DEFCLASSIFICATIONCOLL** (Optional) By default the new definition is classified according to the subtype you assigned it in the `CDR_NAMING_VERSION_OBJ_TYPE`. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of `CDR_CLA_OBJ_TYPES`, which have five attributes, including `CLA_LEVEL_ID` and `CLASSIFICATION_ID`.

If you want the definition to inherit its classifications for a particular level from its parent, enter the classification level ID and, for the `CLASSIFICATION_ID`, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a `CDR_CLA_OBJ_TYPE` for each term, entering the classification level ID and, for the `CLASSIFICATION_ID`, the term ID. Do not enter any values for them.

If you are not creating a new definition, do not enter values here.
- PI_INSTCLASSIFICATIONCOLL** (Optional) By default the new instance is classified according to the subtype you assigned it in the `CDR_NAMING_VERSION_OBJ_TYPE`.

If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID.

If you want the instance to inherit its classifications for a particular level from its parent Work Area, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are not relevant to Programs. Do not enter any values for them.

If you are not creating a new instance, do not enter values here.

Copy Objects Into a Program

Use this API to copy objects into a Program.

Name

CDR_PUB_DF_PROGRAM.CopyObjectIntoProgram

Signature

```
PROCEDURE COPYOBJECTINTOPROGRAM(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_CDRBASEOBJCOLL IN CDR_BASE_OBJ_COLL,
  PI_CDRTARGETCONTAINEROBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PI_CHECKINFLAG IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_CDRBASEOBJCOLL** Collection of objects to be copied.
- **PI_CDRTARGETCONTAINEROBJECT** The target container object.
- **PI_CHECKINFLAG** Flag to indicate if the copied objects are to be checked in.

Modify a Program

Use this API to modify a Program definition or instance. You can modify the name and description.

If you are modifying an instance object, you can also change the 3 REF attribute values to select a different source definition.



Note:

If you are modifying a definition, you must first check it out.

Name

CDR_PUB_DF_PROGRAM.ModifyProgramDetails

Signature

```
PROCEDURE MODIFYPROGRAMDETAILS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_CDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_CDRNAMING (Mandatory) This is an IN OUT parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes.

Check In a Program Definition

Use this API to check in a Program definition.

Name

CDR_PUB_DF_PROGRAM.CheckInProgramDefinition

Signature

```
PROCEDURE CHECKINPROGRAMDEFINITION (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_BASEOBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PI_COMMENT IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Program definition that you want to check in.
The following attributes are required:
COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.
- **PI_COMMENT** (Optional) Enter the reason you are checking in the Program.

Check Out a Program Definition

Use this API to check out a Program definition either directly or through an instance of it.

Name

CDR_PUB_DF_PROGRAM.CheckOutProgram

Signature

```
PROCEDURE CHECKOUTPROGRAM(
  P_API_VERSION IN    NUMBER,
  P_INIT_MSG_LIST IN  VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN       VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN    NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT    VARCHAR2,
  X_MSG_COUNT OUT      NUMBER,
  X_MSG_DATA OUT       VARCHAR2,
  PIO_BASEOBJECT IN OUT  CDR_BASE_OBJ_TYPE,
  PI_COMMENT IN       VARCHAR2,
  PI_ISINSTONLY IN    VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Program that you want to check out. If you are checking out the Program definition directly, enter values to identify the definition.

If you are checking out a Program definition through an instance of it, enter values to identify the instance.

The following attributes are required:

COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.

- **PI_COMMENT** (Optional) Enter the reason you are checking out the Program.
- **PI_ISINSTONLY** Enter \$YESNO\$NO.

Remove a Program

Use this API to remove one or more Program definitions or instances.

Name

CDR_PUB_DF_PROGRAM.RemoveProgram

Signature

```
PROCEDURE REMOVEPROGRAM(
  P_API_VERSION IN    NUMBER,
  P_INIT_MSG_LIST IN  VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN       VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN    NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT    VARCHAR2,
```

```

X_MSG_COUNT OUT NUMBER,
X_MSG_DATA OUT VARCHAR2,
PIO_CDRBASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_CDRBASEOBJCOLL (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES. For each Program that you want to remove, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.

The following attributes are required:

COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

Create a Planned Output for a Log File

Use this API to create a log file Planned Output for a Program.



Note:

You must define a log file Planned Output, which is part of the Program definition, through an instance of the Program.

Name

CDR_PUB_DF_PROGRAM.CreateLogFilePlannedOutput

Signature

```

PROCEDURE CREATELOGFILEPLANNEDOUTPUT(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECODENAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_SOURCECODENAMING (Mandatory) This is a parameter of type cdr_naming_version_obj_type.

The required attributes are:

COMPANY_ID,NAME,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

Assign a Planned Output

Use this API to assign a Planned Output to a Report Set Entry (RSE). If the Planned Output is already assigned to a different RSE, you must identify that RSE. This API then unassigns the Planned Output from the original RSE and reassigns it to the RSE you specify.

Name

CDR_PUB_DF_PROGRAM.AssignPlandPOtoRSEntry

Signature

```
PROCEDURE ASSIGNPIANDPOTORSENTRY (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_RSECOMPANYID IN CDR_NAMINGS.COMPANY_ID%TYPE,
  PI_RSEOBJID IN CDR_NAMINGS.OBJ_ID%TYPE,
  PI_RSEOBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE,
  PI_PIOBJID IN CDR_NAMINGS.OBJ_ID%TYPE,
  PI_POCOMPANYID IN CDR_NAMINGS.COMPANY_ID%TYPE,
  PI_POOBJID IN CDR_NAMINGS.OBJ_ID%TYPE,
  PI_ASGRSEOBJID IN CDR_NAMINGS.OBJ_ID%TYPE,
  PI_ASGRSEOBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_RSECOMPANYID** (Mandatory) Enter the Company ID of the Report Set Entry to which you want to assign the Planned Output. To get your company ID, use CDR_DF_PUB_DEF_CONSTANTS.Current_Company_ID.
- **PI_RSEOBJID** (Mandatory) Enter the object ID of the Report Set Entry to which you want to assign the Planned Output.
- **PI_RSEOBJVER** (Mandatory) Enter the object version of the Report Set Entry to which you want to assign the Planned Output.
- **PI_PIOBJID** (Mandatory) Enter the object ID of the Program instance to which the Planned Output belongs.
- **PI_POCOMPANYID** (Mandatory) Enter the Company ID of the Planned Output.
- **PI_POOBJID** (Mandatory) Enter the object ID of the Planned Output.
- **PI_ASGRSEOBJID** (Optional) If the Planned Output is already assigned to another RSE, enter the object ID of the other Report Set Entry.
- **PI_ASGRSEOBJVER** (Optional) If the Planned Output is already assigned to another RSE, enter the object version of the other Report Set Entry.

Modify a Manual Validation Flag Value

Use this API to change the value of the Program's manual validation (Force Validation Status to Development) flag.

Name

CDR_PUB_DF_PROGRAM. ModifyProgramDetails

Signature

```
PROCEDURE MODIFYPROGRAMDETAILS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_CDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PI_PROGRAMOBJTYPE IN OUT CDR_PROGRAM_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_CDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Program definition whose flag value you want to change.
The following attributes are required: OBJ_ID, OBJ_VER, COMPANY_ID, NS_OBJ_ID, NS_OBJ_VER.
- **PI_PROGRAMOBJTYPE** (Mandatory) This is a parameter of table type CDR_PROGRAM_OBJ_TYPE that contains Program definition attributes.
The required attributes are OBJ_ID, OBJ_VER, COMPANY_ID. Enter values to identify the Program definition whose flag value you want to change and enter the new flag value in the attribute MANUAL_VALIDATION_FLAG_RC. Enter \$yesno\$yes for yes, and \$yesno\$no for no.

Software Source Codes

This is a public interface for Source Code-related operations including creating, modifying, and removing Source Code objects.

- [Create and Modify Source Code](#)

Create and Modify Source Code

This section contains the following topics:

- [Create a Source Code Object](#)
- [Get a Source Code CLOB](#)
- [Modify Source Code](#)
- [Set the Primary Flag to Yes](#)
- [Update a Shareable Flag](#)
- [Remove a Source Code Object](#)

Create a Source Code Object

Use this API to create a new instance of an existing Source Code definition or a new Source Code definition and an instance of it.



Note:

Source Code definitions and instances are always contained in Program definitions. You cannot create a Source Code definition without also creating an instance of it in the same Program definition.

Name

CDR_PUB_DF_SOURCECODE.CreateSourceCode

Signature

```
PROCEDURE CREATESOURCECODE (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SCREF_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PI_CDRSCOBJTYPE IN OUT CDR_SRCCODE_OBJ_TYPE,
  PIO_CDRSCREFOBJTYPE IN OUT CDR_SRCCODE_REF_OBJ_TYPE,
  PI_CREATEOBJECT IN VARCHAR2,
```

```

PI_DEFINITON_SUBTYPE_ID IN      CDR_NAMINGS.OBJECT_SUBTYPE_ID%TYPE,
PI_VLOBMODE IN      VARCHAR2 := NULL,
PIO_CDRSCBLOB IN OUT  CDR_SRCCODE_BLOB_OBJ_TYPE,
PIO_CDRSCCLOB IN OUT  CDR_SRCCODE_CLOB_OBJ_TYPE
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SCREF_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. Enter values for the Source Code instance you are creating. For OBJECT_TYPE_RC enter \$OBJTYPES\$SRCCDEREF.
- **PI_CDRSCOBJTYPE** (Optional) This is a parameter of table type CDR_SRCCODE_OBJ_TYPE that contains object attributes specific to Source Code definitions.
If you are creating a new definition, enter values for the new Source Code definition. The following attributes are required:
TECH_TYPE_ID,SRCCODE_TYPE_RC,SHAREABLE_FLAG_RC,ORACLE_PACKAGE_NAME.

If you are creating an instance of an existing Source Code definition, do not enter any values here.
- **PIO_CDRSCREFOBJTYPE** (Optional) This is a parameter of table type CDR_SRCCODE_REF_OBJ_TYPE that contains object attributes specific to Source Code instances.
If you are creating a new instance, enter values for it.

If you are creating a new Source Code definition only, do not enter any values here.
- **PI_CREATEOBJECT** (Mandatory) Enter INST to create a instance of an existing definition or BOTH to create a new definition and an instance of it.
- **PI_DEFINITON_SUBTYPE_ID** (Optional) Enter a subtype for the Source Code definition. If you do not enter a value, the API creates the definition with the default subtype.
- **PI_VLOBMODE** Enter 'DIRECT' if your source code is already contained in a BLOB or CLOB file. You enter information about it in one of the next two parameters and the API uploads it immediately.
If you enter anything other than 'DIRECT' the API creates a new, empty BLOB and CLOB in the next parameters. It prompts you to paste your source code in and then uploads the BLOB or CLOB.
- **PIO_CDRSCBLOB** This is a compound object of type CDR_SRCCODE_BLOB_OBJ_TYPE.
If the source code is binary, enter its name for the FILE_NAME attribute value and the BLOB itself for the FILE_BLOB attribute value.
- **PIO_CDRSCCLOB** This is a compound object of type CDR_SRCCODE_CLOB_OBJ_TYPE.
If the source code is text-based, enter its name for the FILE_NAME attribute value and the CLOB itself for the FILE_CLOB attribute value.

Get a Source Code CLOB

Use this API to get the source code CLOB.

Name

CDR_PUB_DF_SOURCECODE.GetSourceCode

Signature

```

FUNCTION GETSOURCECODE (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  COMPANYID IN CDR_NAMINGS.COMPANY_ID%TYPE,
  OBJID IN CDR_NAMINGS.OBJ_ID%TYPE,
  OBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE,
  NSOBJID IN CDR_NAMINGS.OBJ_ID%TYPE,
  NSOBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE
) RETURN CLOB;

```

Return

Type CLOB

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **COMPANYID** (Mandatory) Enter your company ID.
- **OBJID** (Mandatory) Enter the object ID of the Source Code definition.
- **OBJVER** (Mandatory) Enter the object version (OBJ_VER) of the Source Code definition.
- **NSOBJID** (Mandatory) Enter the object ID of the Program definition that contains the Source Code definition.
- **NSOBJVER** (Mandatory) Enter the object version (OBJ_VER) of the Program definition that contains the Source Code definition.

Modify Source Code

Use this API to modify a Source Code definition or instance. You can modify the name and description. If you are modifying a Source Code instance, you can also change the 3 REF attribute values to select a different source definition.

Name

CDR_PUB_DF_SOURCECODE.ModifySourceCodeDetails

Signature

```

PROCEDURE MODIFYSOURCECODEDETAILS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SCREF_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PI_CDRSCOBJTYPE IN OUT CDR_SRCCODE_OBJ_TYPE,
  PIO_CDRSCREFOBJTYPE IN OUT CDR_SRCCODE_REF_OBJ_TYPE,

```

```

PI_VLOBMODE IN VARCHA2 := NULL,
PIO_CDRSCBLOB IN OUT CDR_SRCCODE_BLOB_OBJ_TYPE,
PIO_CDRSCCLOB IN OUT CDR_SRCCODE_CLOB_OBJ_TYPE
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SCREF_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Source Code definition or instance and enter new values for the attributes you want to modify. You can change the name or description for either the definition or instance. For an instance you can also change to a different underlying source definition by entering values for the new definition in the three REF attributes.

Note:

Neither Source Code definitions nor instances can have a validation status or a version label. All attributes are required.

- **PI_CDRSCOBJTYPE** (Mandatory) This is a parameter of table type CDR_SRCCODE_OBJ_TYPE that contains object attributes specific to Source Code definitions.
If you are modifying a Source Code definition, enter values to identify the definition and enter new values for the attributes you want to modify.
You can modify SHAREABLE_FLAG_RC, ORACLE_PACKAGE_NAME, and ORACLE_PROCEDURE_NAME. All attributes are required.
- **PIO_CDRSCREFOBJTYPE** (Mandatory) This is a parameter of table type CDR_SRCCODE_REF_OBJ_TYPE that contains object attributes specific to Source Code instances.
If you are modifying a Source Code instance, enter values to identify the instance and enter new values for the attributes you want to modify. You can modify PRIMARY_FLAG_RC and FILEREF. All attributes are required.
- **PI_VLOBMODE** Enter 'DIRECT' if your source code is already contained in a BLOB or CLOB file. You enter information about it in one of the next two parameters and the API uploads it immediately.
If you enter anything other than 'DIRECT' the API creates a new, empty BLOB and CLOB in the next parameters. It prompts you to paste in your source code and then uploads the BLOB or CLOB.
- **PIO_CDRSCBLOB** This is a compound object of type CDR_SRCCODE_BLOB_OBJ_TYPE.
If the source code is binary, enter its name for the FILE_NAME attribute value and the BLOB itself for the FILE_BLOB attribute value.
- **PIO_CDRSCCLOB** This is a compound object of type CDR_SRCCODE_CLOB_OBJ_TYPE.
If the source code is text-based, enter its name for the FILE_NAME attribute value and the CLOB itself for the FILE_CLOB attribute value. Enter CLOB if the source code file is a character large object.

Set the Primary Flag to Yes

Use this API to set the Primary Flag attribute of a specified Source Code instance to Yes. If any other Source Code instance in the parent Program is currently set to Yes, the API resets its flag to No.

Name

CDR_PUB_DF_SOURCECODE.SetPrimaryFlagRC

Signature

```
PROCEDURE SETPRIMARYFLAGRC (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_CDRSCREFBASEOBJTYPE IN CDR_BASE_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PI_CDRSCREFBASEOBJTYPE (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Source Code instance whose PRIMARY_FLAG_RC you want to set to \$YESNO\$YES.

The following attributes are required:

COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAME_SPACE_OBJ_VER.

Update a Shareable Flag

Use this API to set the Shareable attribute for a Source Code definition.

Name

CDR_PUB_DF_SOURCECODE.UpdateShareableFlagRC

Signature

```
PROCEDURE UPDATESHAREABLEFLAGRC (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_CDRSCBASEOBJTYPE IN OUT CDR_BASE_OBJ_TYPE,
  PI_CHANGESTATUSTO IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_CDRSCBASEOBJTYPE** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Source Code definition that you want to make sharable or not sharable.
The following attributes are required:
COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.
- **PI_CHANGESTATUS** (Mandatory) Enter SET to set the SHAREABLE_FLAG_RC to \$YESNO\$YES or RESET to set the SHAREABLE_FLAG_RC to '\$YESNO\$NO'.

Remove a Source Code Object

Use this API to remove one or more Source Code definitions or instances.

Name

CDR_PUB_DF_SOURCECODE.RemoveSourceCode

Signature

```
PROCEDURE REMOVESOURCECODE (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_CDRBASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PIO_CDRBASEOBJCOLL (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES.

For each Source Code that you want to remove, initialize a CDR_BASE_OBJ_TYPE and then extend the collection. The following attributes are required:

COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

13

Tables

This is a public interface for all operations related to Tables, Columns, and Constraints; including creation, deletion, modification, and checking in and out of these objects.

This chapter contains this section:

- [Create and Modify Tables](#)

Create and Modify Tables

This section contains the following topics:

- [Create a Table Definition](#)
- [Create a Table Instance](#)
- [Create a Temporary Blob](#)
- [Create a Table Column](#)
- [Modify a Table Column](#)
- [Create a Table Constraint](#)
- [Modify a Table Constraint](#)
- [Modify a Table Definition](#)
- [Create a Table Descriptor](#)
- [Modify a Table Descriptor](#)
- [Modify a Table Instance](#)
- [Reorder a Column](#)
- [Upload a Table Descriptor or Column](#)
- [Check Out a Table](#)
- [Check In a Table](#)
- [Undo Check Out for a Table Definition](#)
- [Remove a Single Object](#)

Create a Table Definition

Use this API to create a Table definition.

Name

CDR_PUB_DF_TABLE.CreateTableDefinition

Signature

```
PROCEDURE CREATETABLEDEFINITION(  
    P_API_VERSION IN NUMBER,
```

```

P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT VARCHAR2,
X_MSG_COUNT OUT NUMBER,
X_MSG_DATA OUT VARCHAR2,
PIO_NAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
PIO_TABLE IN OUT CDR_TABLE_OBJ_TYPE,
PI_INSTANCESUBTYPEID IN NUMBER,
PI_DEFCCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL,
PI_INSTCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. For OBJECT_TYPE_RC enter \$OBJTYPES\$TABLE.
- **PIO_TABLE** (Optional) This is a parameter of table type CDR_TABLE_OBJ_TYPE that contains object attributes specific to Tables.
If you are creating a new definition, enter values for the new Table. The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER, ORACLE_NAME, SAS_NAME, SASV6FLAGRC = '\$YESNO\$NO', SNAPSHOTFLAGRC = '\$YESNO\$YES', BLINDINGFLAGRC = '\$YESNO\$YES', PROCESSTYPERC = '\$PROCESSTYPES\$STAGINGWAUDIT'

If you are creating an instance of an existing Table, do not enter any values here.

- **PI_INSTANCESUBTYPEID** (Mandatory) Enter NULL here.
- **PI_DEFCCLASSIFICATIONCOLL** (Optional) By default the new definition is classified according to the subtype you assigned it in the CDR_NAMING_VERSION_OBJ_TYPE. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID.

If you want the definition to inherit its classifications for a particular level from its parent, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID.

The PAR_ attributes are not relevant to Tables. Do not enter any values for them.

- **PI_INSTCLASSIFICATIONCOLL** (Mandatory) Enter NULL because you are creating a Table definition.

Create a Table Instance

Use this API to create a Table Instance.

Name

CDR_PUB_DF_TABLE.CreateTableInstance

Signature

```
PROCEDURE CREATETABLEINSTANCE (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_NAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PIO_TABLE_INSTANCE IN OUT CDR_TABLE_REF_OBJ_TYPE,
  PI_CREATETYPE IN VARCHAR2,
  PI_INSTANCESUBTYPEID IN NUMBER,
  PI_DEFCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL,
  PI_INSTCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory) This is a parameter of table type `CDR_NAMING_VERSIONS_OBJ_TYPE` that contains CDR Naming Version attributes. For `OBJECT_TYPE_RC` enter `$OBJTYPES$TABLEREF`.
- **PIO_TABLE_INSTANCE** (Optional) This is a parameter of table type `CDR_TABLE_OBJ_TYPE` that contains object attributes specific to Table instances. The following attributes are required:
`COMPANY_ID,OBJ_ID,OBJ_VER,ORACLE_NAME,SAS_NAME SASV6FLAGRC =`
`'$YESNO$NO', SNAPSHOTFLAGRC= '$YESNO$YES', BLINDINGFLAGRC=`
`'$YESNO$YES',PROCESSTYPERC =`
`'$PROCESSTYPES$STAGINGWAUDIT',BLINDINGSTATUSRC=`
`'$BLIND_STATS$BLINDED',COMPRESSFLAGRC=`
`'$YESNO$NO',GENERATIONSTATUSRC= '$YESNO$NO'.`
- **PI_CREATETYPE** (Mandatory) Enter `INST` to create a Table instance of an existing Table definition. Enter `BOTH` to create a Table definition and a Table instance of it.
- **PI_INSTANCESUBTYPEID** (Mandatory) Enter the `SUBTYPE_ID` of the Table instance.
- **PI_DEFCLASSIFICATIONCOLL** (Optional) By default the new definition is classified according to the subtype you assigned it in the `CDR_NAMING_VERSION_OBJ_TYPE`. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of `CDR_CLA_OBJ_TYPES`, which have 5 attributes, including `CLA_LEVEL_ID` and `CLASSIFICATION_ID`.

If you want the definition to inherit its classifications for a particular level from its parent, enter the classification level ID and, for the `CLASSIFICATION_ID`, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a `CDR_CLA_OBJ_TYPE` for each term, entering the classification level ID and, for the `CLASSIFICATION_ID`, the term ID. The `PAR_` attributes are not relevant to Tables. Do not enter any values for them. If you are not creating a new definition, do not enter values here.

- **PI_INSTCLASSIFICATIONCOLL** (Optional) By default the new instance is classified according to the subtype you assigned it in the `PI_INSTANCE_SUBTYPE_ID`. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of `CDR_CLA_OBJ_TYPES`, which have 5 attributes, including `CLA_LEVEL_ID` and `CLASSIFICATION_ID`.

If you want the instance to inherit its classifications for a particular level from its parent Work Area, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID.

The PAR_ attributes are not relevant to Tables. Do not enter any values for them. If you are not creating a new instance, do not enter values here.

Create a Temporary Blob

Use this API to create a temporary BLOB in a BLOB Table. Call this API before you upload Columns or Table Descriptors using the UPLOADOPERATORCOLUMNS API for a SAS or CPORT file, or before creating a Table for a SAS dataset.

Name

CDR_PUB_DF_TABLE.CreateTempBlob

Signature

```
PROCEDURE CREATETEMPBLOB(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_TMPBLOBOBJ IN OUT CDR_TEMP_BLOBS_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_TMPBLOBOBJ (Mandatory) This is parameter of table type CDR_TEMP_BLOBS_OBJ_TYPE that contains information about the BLOB.

The required attributes are: FILE_NAME, FILE_BLOB

Create a Table Column

Use this API to create a Table Column. As with any other object, you can create an instance of an existing Variable or create a new Variable and Column. (Variable is the definition object for Columns.)

Name

CDR_PUB_DF_TABLE.CreateColumn

Signature

```
PROCEDURE CREATECOLUMN(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
```

```

X_RETURN_STATUS OUT    VARCHAR2,
X_MSG_COUNT OUT      NUMBER,
X_MSG_DATA OUT       VARCHAR2,
PIO_NAMING IN OUT     CDR_NAMING_VERSION_OBJ_TYPE,
PIO_VARIABLE IN OUT   CDR_VAR_OBJ_TYPE,
PIO_COLUMN IN OUT     CDR_COLUMNS_OBJ_TYPE,
PI_CREATETYPE IN      VARCHAR2,
PI_DEFCCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. For OBJECT_TYPE_RC enter \$OBJTYPES\$COLUMN.
- **PIO_VARIABLE** (Mandatory) This is a parameter of table type CDR_VAR_OBJ_TYPE that contains object attributes specific to Variables. The following attributes are required: ORACLE_NAME, ORACLE_DATATYPE_RC, LENGTH, PRECISION, SAS_V8_NAME, SAS_LABEL, SAS_FORMAT, NULLABLE_FLAG_RC, DEFAULT_VALUE.
- **PIO_COLUMN** (Mandatory) This is a parameter of table type CDR_COLUMNS_OBJ_TYPE that contains object attributes specific to Columns. The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER, POSITION, SAS_LABEL, NULLABLE_FLAG_RC.
- **PI_CREATETYPE** (Mandatory) Enter INST to create only a Column of an existing definition (Variable); or BOTH to create a new Column and Variable.
- **PI_DEFCCLASSIFICATIONCOLL** (Optional) By default the new definition is classified according to the subtype assigned it in the CDR_NAMING_VERSION_OBJ_TYPE. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID.

If you want the definition to inherit its classifications for a particular level from its parent, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are not relevant to Columns. Do not enter any values for them.

If you are not creating a new definition, do not enter values here.

Modify a Table Column

Use this API to modify a column in a Table definition.

Name

CDR_PUB_DF_TABLE.ModifyColumn

Signature

```

PROCEDURE modifyColumn(
p_api_version IN NUMBER
,p_init_msg_list IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
,p_commit IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE

```

```
,p_validation_level IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
,x_return_status OUT NOCOPY VARCHAR2
,x_msg_count OUT NOCOPY NUMBER
,x_msg_data OUT NOCOPY VARCHAR2
, pio_naming IN OUT NOCOPY cdr_naming_version_obj_type
, pio_column IN OUT NOCOPY cdr_columns_obj_type
) ;
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains object attributes. Enter values you want to change. For OBJECT_TYPE_RC enter \$OBJTYPES\$COLUMN.
- **PIO_COLUMN** (Mandatory) This is a parameter of table type CDR_COLUMNS_OBJ_TYPE that contains object attributes specific to Columns. You can change the Column's name, description and values for the NULLABLEFLAGRC, and SAS_LABEL attributes. Valid values for NULLABLEFLAGRC are \$YESNO\$YES or \$YESNO\$NO.

Create a Table Constraint

Use this API to create a constraint for a Table definition or a Table instance.

Name

CDR_PUB_DF_TABLE.CreateTableConstraint

Signature

```
PROCEDURE CREATETABLECONSTRAINT(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_NAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PIO_CONSTRAINT IN OUT CDR_TABLE_CONS_OBJ_TYPE,
  PI_CONSTRAINTCOLUMNS IN OUT CDR_TABLE_CONCOLS_LIST_COLL,
  PI_VALS IN CDR_VALS_COLL
) ;
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. Enter \$OBJTYPES\$TABLECNSTR for OBJECT_TYPE_RC.
- **PIO_CONSTRAINT** (Mandatory) This is a parameter of table type CDR_TABLE_CONS_OBJ_TYPE. You must enter values for CONSTRAINT_TYPE_RC. The possible values are: \$CONSTRAINTYPES\$CHECK, \$CONSTRAINTYPES\$NUINDEX, \$CONSTRAINTYPES\$PRIMARYKEY, and \$CONSTRAINTYPES\$UNIQUE.

- **PI_CONSTRAINTCOLUMNS** (Mandatory) This is a collection of table type `CDR_TABLE_CONCOLS_OBJ_TYPE`. Identify the Table and the Table's columns where you want to apply the Constraints. Depending on the Constraint, you must also provide values for attributes that define Foreign Key, or that identify the List of Values object to store the values for a CHECK Constraint.
The following attributes are required:
`TABC_COMPANY_ID, TABC_OBJ_ID, TABC_OBJ_VER, FK_COL_COMPANY_ID, FK_COL_OBJ_ID, FK_COL_OBJ_VER, POSITION, COL_COMPANY_ID, COL_OBJ_ID, COL_OBJ_VER, LOV_COMPANY_ID, LOV_ID, LOV_VER`
- **PI_VALS** (Optional) This is a collection of `CDR_VAL_OBJ_TYPE` that contains the values for a CHECK Constraint.

Modify a Table Constraint

Use this API to modify a Table constraint. You need to check out the Table definition to modify the constraint.

```
PROCEDURE modifyTableConstraint(
  p_api_version IN NUMBER
  ,p_init_msg_list IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  ,p_commit IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  ,p_validation_level IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
  ,x_return_status OUT NOCOPY VARCHAR2
  ,x_msg_count OUT NOCOPY NUMBER
  ,x_msg_data OUT NOCOPY VARCHAR2
  ,pio_naming IN OUT NOCOPY cdr_naming_version_obj_type
  ,pio_constraint IN OUT NOCOPY cdr_table_cons_obj_type
  ,pi_constraintColumns IN cdr_table_concols_list_coll
  ,pi_vals IN cdr_vals_coll
) ;
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory) This is a parameter of table type `CDR_NAMING_VERSIONS_OBJ_TYPE` that contains CDR Naming Version attributes. Enter values to identify the Table Constraint and enter new values for the attributes you want to modify. Enter `$OBJTYPES$TABLECNSTR` for `OBJECT_TYPE_RC`.
- **PIO_CONSTRAINT** (Mandatory) This is a parameter of table type `CDR_TABLE_CONS_OBJ_TYPE`. Enter values you want to change. You can change the name, description, and values specific to the constraint type; for example, values for the CHECK constraint. You cannot modify the constraint type.
- **PI_CONSTRAINTCOLUMNS** (Mandatory) This is a collection of table type `CDR_TABLE_CONCOLS_OBJ_TYPE`. Identify the table and the table's columns where you want to apply the constraints.
- **PI_VALS** (Optional) This is a collection of `CDR_VAL_OBJ_TYPE` that contains the values for a CHECK constraint. It is not relevant to other constraints.

Modify a Table Definition

Use this API to modify a Table definition. You need to check out the Table definition that you want to modify.

Name

CDR_PUB_DF_TABLE.ModifyTableDefinition

Signature

```
PROCEDURE MODIFYTABLEDEFINITION(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_NAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PIO_TABLE IN OUT CDR_TABLE_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Table definition and enter new values for the attributes you want to modify. All attributes are required.

 Note:

Use separate APIs for modifying the validation status and the version label:
CDR_PUB_VL_VALIDATION.UPDATE_VAL_STATUS and
CDR_PUB_DF_NAMING.UPDATEVERSIONLABEL.

- **PIO_TABLE** (Mandatory) This is a parameter of table type CDR_TABLE_OBJ_TYPE that contains attributes specific to Table definitions. Enter the values that you want to change.

Create a Table Descriptor

Use this API to create a Table Descriptor. Table Descriptors are owned by executable object definitions and Business Area definitions and are required to map to source and target Table instances. You must check out the parent object to create a Table Descriptor.

Name

CDR_PUB_DF_TABLE.CreateTableDescriptor

Signature

```
p_api_version IN NUMBER
,p_init_msg_list IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
,p_commit IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
,p_validation_level IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
,x_return_status OUT NOCOPY VARCHAR2
,x_msg_count OUT NOCOPY NUMBER
,x_msg_data OUT NOCOPY VARCHAR2
, pio_naming IN OUT NOCOPY cdr_naming_version_obj_type
, pio_table_descriptor IN OUT NOCOPY cdr_table_desc_obj_type
, pi_createType IN VARCHAR2
, pi_instanceSubTypeId IN NUMBER
```

```
, pi_defClassificationColl IN CDR_CLASSIFICATIONS_COLL
, pi_instClassificationColl IN CDR_CLASSIFICATIONS_COLL
) ;
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Table Descriptor and enter new values for the attributes you want to create. All attributes are required. See [CDR Naming Version Object Type](#). For OBJECT_TYPE_RC enter \$OBJTYPES\$TABLEDESCRIPTOR. If you are creating a Table Descriptor from an existing Table definition, enter values for the table definition in the CDR naming attributes. REF_COMPANY_ID, REF_OBJ_ID, REF_OBJ_VER.
If you are creating a new Table definition, leave these attributes blank.
- **PIO_TABLE_DESCRIPTOR** (Mandatory) This is a parameter of table type CDR_TABLE_OBJ_TYPE that contains attributes specific to Table Descriptors, including:
 - LIBREF: Enter Target or Source.
 - TARGET_OPER_FLAG_RC: Enter \$YESNO\$YES
 - TARGET_AS_DATASET_FLAG_RC: Enter \$YESNO\$NO
 - PROCESS_TYPE_RC: Enter \$PROCESSTYPES\$RELOAD
 - REVEAL_AUDIT_FLAG_RC: Enter \$YESNO\$NO
 - SEQ: Enter 1.
- **PI_CREATETYPE** (Mandatory)
 - Enter INST to create a Table instance of an existing Table definition.
 - Enter BOTH to create a Table definition and a Table instance of it.
- **PI_INSTANCESUBTYPEID** (Mandatory) Enter NULL.
- **PI_DEFCLASSIFICATIONCOLL** (Optional) To inherit its classifications for a particular level from its parent, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero). The PAR_ attributes are not relevant. Do not enter any values for them. Or enter NULL.
- **PI_INSTCLASSIFICATIONCOLL** (Mandatory) Enter NULL because you are creating a Table definition.

Modify a Table Descriptor

Use this API to modify a Table Descriptor. You need to check out the parent object of the Table Descriptor in order to modify it.

Name

CDR_PUB_DF_TABLE.ModifyTableDescriptor

Signature

```
PROCEDURE MODIFYTABLEDESCRIPTOR(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
```

```

X_RETURN_STATUS OUT    VARCHAR2,
X_MSG_COUNT OUT      NUMBER,
X_MSG_DATA OUT       VARCHAR2,
PIO_NAMING IN OUT    CDR_NAMING_VERSION_OBJ_TYPE,
PIO_TABLE_DESCRIPTOR IN OUT CDR_TABLE_DESC_OBJ_TYPE
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Table Descriptor and enter new values for the attributes you want to modify. All attributes are required.

Note:

Use separate APIs for modifying the validation status and the version label: CDR_PUB_VL_VALIDATION.UPDATE_VAL_STATUS and CDR_PUB_DF_NAMING.UPDATEVERSIONLABEL.

- **PIO_TABLE_DESCRIPTOR** (Mandatory) This is a parameter of table type CDR_TABLE_OBJ_TYPE that contains attributes specific to Table Descriptors. Enter the values that you want to change.

Modify a Table Instance

Use this API to modify a Table Instance.

Name

CDR_PUB_DF_TABLE.ModifyTableInstance

Signature

```

PROCEDURE MODIFYTABLEINSTANCE(
  P_API_VERSION IN    NUMBER,
  P_INIT_MSG_LIST IN  VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN      VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN  NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT   VARCHAR2,
  X_MSG_COUNT OUT      NUMBER,
  X_MSG_DATA OUT       VARCHAR2,
  PIO_NAMING IN OUT    CDR_NAMING_VERSION_OBJ_TYPE,
  PIO_TABLE_INSTANCE IN OUT CDR_TABLE_REF_OBJ_TYPE
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Table instance and enter new values for the attributes you want to modify. All attributes are required.

 Note:

Use separate APIs for modifying the validation status and the version label:
 CDR_PUB_VL_VALIDATION.UPDATE_VAL_STATUS and
 CDR_PUB_DF_NAMING.UPDATEVERSIONLABEL.

- **PIO_TABLE_INSTANCE** (Mandatory) This is a parameter of table type CDR_TABLE_OBJ_TYPE that contains attributes specific to Table instances. Enter the values that you want to change.

Reorder a Column

Use this API to reorder a Table's columns. You need to check out the Table definition whose columns you want to reorder.

Name

CDR_PUB_DF_TABLE.ReorderColumns

Signature

```
PROCEDURE REORDERCOLUMNS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_REORDEROBJCOLL IN CDR_REORDER_OBJ_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PI_REORDEROBJCOLL (Mandatory) This is a collection of CDR_REORDER_OBJ_TYPE that contains the Column objects that you want to reorder. The value for ENTRY_NUMBER must be NULL. Add the Columns to the collection in the new order in which you want them.

Upload a Table Descriptor or Column

Use this API to upload Columns and/or a Table Descriptor.

Name

CDR_PUB_DF_TABLE.UploadOperatorColumns

Signature

```
PROCEDURE UPLOADOPERATORCOLUMNS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
```

```

PI_COMPID IN      NUMBER,
PI_NSOBJID IN     NUMBER,
PI_NSOBJVER IN    NUMBER,
PI_OBJID IN       NUMBER,
PI_OBJVER IN      NUMBER,
PI_NVCOLL IN      CDR_NAME_VALUE_PAIR_COLL
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPID** (Mandatory) Enter the COMPANY_ID of the Column or Table Descriptor.
- **PI_NSOBJID** (Mandatory) Enter the Namespace OBJ_ID of the Column or Table Descriptor.
- **PI_NSOBJVER** (Mandatory) Enter the Namespace OBJ_VER of the Column or Table Descriptor.
- **PI_OBJID** (Mandatory) Enter the OBJ_ID of the Column or Table Descriptor.
- **PI_OBJVER** (Mandatory) Enter the OBJ_VER of the Column or Table Descriptor.
- **PI_NVCOLL** (Mandatory) This is a collection of CDR_NAME_VALUE_PAIR_OBJ_TYPE that contains name value pairs for the variable in LSH database to store the uploaded Columns and/or Table Descriptor.

You must call CREATETEMPBLOB API before you use this API.

For SAS/C-PORT files, the variable name is the TMP_BLOB_ID which is defined after you call CREATETEMPBLOB API. For other uploads, the variable name is NULL.

Check Out a Table

Use this API to check out a Table definition or definition and instance.

Name

CDR_PUB_DF_TABLE.Checkout

Signature

```

Procedure checkout(
p_api_version IN NUMBER
,p_init_msg_list IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
,p_commit IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
,p_validation_level IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
,x_return_status OUT NOCOPY VARCHAR2
,x_msg_count OUT NOCOPY NUMBER
,x_msg_data OUT NOCOPY VARCHAR2
, pi_baseObject IN OUT NOCOPY cdr_base_obj_type
, pi_comment IN VARCHAR2
, pi_isInstOnly IN VARCHAR2
) ;

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. You can enter values to identify either the Table definition or an instance of it:

- Pass the Table definition details if you want to check out and subsequently modify only the definition.
- Pass the details of an instance of the Table definition if you want the instance to point to the new version of the Table definition.

The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.

NAMESPACE_OBJ_ID. If you are entering information about a Table definition, enter the object ID of its containing Application Area. If you are entering information about a Table instance, enter the object ID of its containing Work Area.

NAMESPACE_OBJ_VER. If you are entering information about a Table definition, enter the object version number of its containing Application Area. If you are entering information about a Table instance, enter the object version number of its containing Work Area.

- **PI_COMMENT** (Optional) Enter the reason you are checking out the Table.
- **PI_ISINSTONLY** Enter \$YESNO\$NO if you are checking out only the definition. Enter \$YESNO\$YES if you are checking out the definition through its instance.

Check In a Table

Use this API to check in a Table Object.

Name

CDR_PUB_DF_TABLE.CheckIn

Signature

```
PROCEDURE CHECKIN(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_BASEOBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PI_COMMENT IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Table definition that you want to check in.
The following attributes are required:
COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.
- **PI_COMMENT** (Optional) Enter the reason you are checking in the Table.

Undo Check Out for a Table Definition

Use this API to undo a check out for a Table Definition.

Name

CDR_PUB_DF_TABLE.UndoCheckOut

Signature

```
PROCEDURE UNDOCHECKOUT (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT NOCOPY VARCHAR2,
  X_MSG_COUNT OUT NOCOPY NUMBER,
  X_MSG_DATA OUT NOCOPY VARCHAR2,
  PIO_BASEOBJECT IN OUT NOCOPY CDR_BASE_OBJ_TYPE,
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

- **PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE that contains object attributes. Enter values to identify the Table definition that you want to undo check out.
The required attributes are: COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.

Remove a Single Object

Use this API to remove a single object of any of the following types: Table definition, Table instance, Table Descriptor, Column, or a Constraint.

Name

CDR_PUB_DF_TABLE.Remove

Signature

```
PROCEDURE REMOVE (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_NAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_NAMING (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES. For each object that you want to remove, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.

The following attributes are required:

COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.

Parameters

This section contains the following topics:

- [Define and Modify Parameters](#)
- [Define Parameter Relations](#)

Define and Modify Parameters

This is a public interface for operations involving defined Parameter objects. For further information, see the chapter on Parameters in the *Oracle Life Sciences Data Hub Application Developer's Guide*.

This section contains the following topics:

- [Create a Parameter](#)
- [Check Out a Parameter](#)
- [Check In a Parameter](#)
- [Get Displayed Parameter Values](#)

Create a Parameter

Use this API to create a parameter instance or definition or both the parameter instance and its definition.

Name

CDR_PUB_DF_PARAMETER.CreateParameter

Signature

```
PROCEDURE CREATEPARAMETER( P_API_VERSION IN NUMBER, P_INIT_MSG_LIST IN
VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 :=
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER :=
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT VARCHAR2,
X_MSG_COUNT OUT NUMBER, X_MSG_DATA OUT VARCHAR2, PIO_PARAMNAMING IN OUT
CDR_NAMING_VERSION_OBJ_TYPE, PIO_CDRPARAMOBJTYPE IN OUT CDR_PARAMETER_OBJ_TYPE,
PI_CREATE_OBJECT IN VARCHAR2, PI_INSTANCE_SUBTYPE_ID IN
CDR_NAMINGS.OBJECT_SUBTYPE_ID%TYPE, PI_PARENTNAMING IN OUT CDR_BASE_OBJ_TYPE,
PO_DEFCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL );
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_PARAMNAMING** (Mandatory) If you are creating a new instance of an existing Parameter Set definition (and instances of all the Parameters in the Parameter Set definition), enter values to identify the Parameter Set definition. For OBJECT_TYPE_RC enter \$OBJTYPES\$PARAMSETREF.
If you are creating a single Parameter, enter values for the Parameter definition you want to create or, if you are creating an instance of an existing Parameter definition, enter

values to identify the definition you want to create an instance of. For OBJECT_TYPE_RC enter \$OBJTYPES\$PARAMETER if you are creating a definition only; \$OBJTYPES\$PARAMREF if you are creating an instance of an existing definition; and NULL if you are creating a new definition and an instance of it.

The following attributes are required: COMPANY_ID, OBJECT_TYPE_RC, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, NAMESPACE_START_OBJ_VER, NAMESPACE_END_OBJ_VER, OWNING_LOCATION_RC, CHECKED_OUT_FLAG_RC, CHECKED_OUT_ID, OBJECT_SUBTYPE_ID, DESCRIPTION, REF_COMPANY_ID, REF_OBJ_ID, REF_OBJ_VER, OBJECT_VERSION_NUMBER, VALIDATION_STATUS_RC, VERSION_LABEL.

- **PIO_CDRPARAMOBJTYPE** (Optional) This is a parameter of table type CDR_PARAMETER_OBJ_TYPE that contains Parameter-specific attributes. If you are creating an instance of an existing Parameter Set, do not enter any values here. If you are creating a single Parameter, enter values for the Parameter definition you want to create or, if you are creating an instance of an existing definition, enter values to identify the definition you want to create an instance of.

The following attributes are required:

For simple parameter, no LOV: COMPANY_ID, PROMPT, INPUT_OUTPUT_RC, READ_ONLY_FLAG_RC, VISIBLE_FLAG_RC, MANDATORY_FLAG_RC, DEFAULT_VALUE, POSITION, PARAM_TYPE_RC, AUTO_SHARE_FIELD_FLAG_RC.

For static LOV type parameter: COMPANY_ID, PROMPT, INPUT_OUTPUT_RC, READ_ONLY_FLAG_RC, VISIBLE_FLAG_RC, MANDATORY_FLAG_RC, DEFAULT_VALUE, POSITION, PARAM_TYPE_RC, AUTO_SHARE_FIELD_FLAG_RC, LOV_COMPANY_ID, LOV_ID, LOV_VER, LOV_MULTI_FLAG_RC, ALLOWED_VALUES_RC, VALIDATION_RULE_RC, VAL_PRG_INST_COMPANY_ID, VAL_PRG_INST_ID, VAL_PRG_INST_VER, VAL_SC_REF_COMPANY_ID, VAL_SC_REF_ID, VAL_SC_REF_VER.

For programatic LOV type parameter: COMPANY_ID, PROMPT, INPUT_OUTPUT_RC, READ_ONLY_FLAG_RC, VISIBLE_FLAG_RC, MANDATORY_FLAG_RC, DEFAULT_VALUE, POSITION, PARAM_TYPE_RC, AUTO_SHARE_FIELD_FLAG_RC, LOV_PRG_INST_COMPANY_ID, LOV_PRG_INST_ID, LOV_PRG_INST_VER, LOV_SC_REF_COMPANY_ID, LOV_SC_REF_ID, LOV_SC_REF_VER, LOV_MULTI_FLAG_RC, ALLOWED_VALUES_RC, VALIDATION_RULE_RC, VAL_PRG_INST_COMPANY_ID, VAL_PRG_INST_ID, VAL_PRG_INST_VER, VAL_SC_REF_COMPANY_ID, VAL_SC_REF_ID, VAL_SC_REF_VER.

For classification LOV type parameter: COMPANY_ID, PROMPT, INPUT_OUTPUT_RC, READ_ONLY_FLAG_RC, VISIBLE_FLAG_RC, MANDATORY_FLAG_RC, DEFAULT_VALUE, POSITION, PARAM_TYPE_RC, AUTO_SHARE_FIELD_FLAG_RC, LOV_CLA_LEVEL_ID, LOV_DEFAULT_CLA_ID, LOV_MULTI_FLAG_RC, ALLOWED_VALUES_RC, VALIDATION_RULE_RC, VAL_PRG_INST_COMPANY_ID, VAL_PRG_INST_ID, VAL_PRG_INST_VER, VAL_SC_REF_COMPANY_ID, VAL_SC_REF_ID, VAL_SC_REF_VER.

- **PI_CREATE_OBJECT** (Mandatory) Enter DEFN to create a Parameter definition only; INST to create a Parameter instance only; BOTH to create a Parameter definition and an instance of it; or PARAMSET if you are creating a new instance of a Parameter Set.
- **PI_INSTANCE_SUBTYPE_ID** (Optional) If you are creating an instance of a single Parameter, enter the ID for the subtype you want to give the instance. If you are creating a Parameter Set instance, do not enter a value here.
- **PI_PARENTNAMING** (Optional) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the object (for example, the Program or Report Set) that contains the Parameter definition.

The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER. If you are creating an instance of a Parameter Set, do not enter a value here.

- **PO_DEFCLASSIFICATIONCOLL** (Optional) By default the new definition is classified according to the subtype you assigned it in the CDR_NAMING_VERSION_OBJ_TYPE. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID.
If you want the definition to inherit its classifications for a particular level from its parent, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero). If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are not relevant to Parameters. Do not enter any values for them. If you are not creating a new definition, do not enter values here.

Check Out a Parameter

Use this API to check out a Parameter definition.

Name

CDR_PUB_DF_PARAMETER.CheckOutParameter

Signature

```
PROCEDURE CHECKOUTPARAMETER( P_API_VERSION IN NUMBER, P_INIT_MSG_LIST IN
VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 :=
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER :=
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT VARCHAR2,
X_MSG_COUNT OUT NUMBER, X_MSG_DATA OUT VARCHAR2, PIO_CDRNAMING IN OUT
CDR_BASE_OBJ_TYPE, PI_COMMENT IN VARCHAR2, PI_ISINSTONLY IN VARCHAR2 );
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_CDRNAMING** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE that contains CDR Naming attributes. Enter values to identify the Parameter you want to check out. The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.
- **PI_COMMENT** (Optional) Enter an explanation of why you are checking out the Parameter.
- **PI_ISINSTONLY** (Mandatory) Enter \$YESNO\$NO.

Check In a Parameter

Use this API to explicitly check in a Parameter definition.

Name

CDR_PUB_DF_PARAMETER.CheckInParameter

Signature

```
PROCEDURE CHECKINPARAMETER( P_API_VERSION IN NUMBER, P_INIT_MSG_LIST IN
VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 :=
```

```
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER :=
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT VARCHAR2,
X_MSG_COUNT OUT NUMBER, X_MSG_DATA OUT VARCHAR2, PIO_CDRNAMING IN OUT
CDR_BASE_OBJ_TYPE, PI_COMMENT IN VARCHAR2 );
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_CDRNAMING** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE that contains CDR Naming attributes. Enter values to identify the Parameter you want to check out. The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.
- **PI_COMMENT** (Optional) Enter a checkin comment.

Get Displayed Parameter Values

Use this API to get the Parameter value(s) that must be displayed in the submission Execution Setup in cases where the displayed value differs from the value used internally: for a Parameter with a classification list of values, this API returns a comma-separated list of the terms in the appropriate classification level (instead of the term_id used internally); for a Report Set Entry Title Parameter, the API returns the title (instead of the RSE obj_id); and for a Parameter with a look-up value, the API returns a display value; for example, 'Yes' instead of \$YESNO\$YES. You can also use this API to populate a default value for a Parameter in an Execution Setup.

Name

CDR_PUB_DF_PARAMETER.GetDefaultCLAVvalue

Signature

```
FUNCTION GETDEFAULTCLAVVALUE( P_API_VERSION IN NUMBER, P_INIT_MSG_LIST IN
VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 :=
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER :=
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, PALLOWEDVALUE IN
CDR_PARAMETERS.ALLOWED_VALUES_RC%TYPE, PDEFAULTVALUE IN VARCHAR2 ) RETURN
VARCHAR2;
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **P_COMMIT** (Optional) Accept the default value (FND_API.G_FALSE) to ensure that this individual API does not commit upon completion. Pass FND_API.G_TRUE to override the default behavior.
- **P_VALIDATION_LEVEL** (Optional) Accept the default value to perform full validation. No other values are currently supported.
- **PALLOWEDVALUE** (Optional) To get the allowed values for a Parameter with a classification LOV, enter \$PARAMALLOWVALS\$CLALOV. To get the title for a Report Set Entry, enter \$PARAMALLOWVALS\$ENTRYLOV. To get a look-up value or enter a default value, do not enter a value here.
- **PDEFAULTVALUE** (Optional) To get the allowed values for a Parameter with a classification LOV, enter the level ID of the Parameter's LOV. To get a look-up value, enter \$PARAMALLOWVALS\$LOV. To get the title for a Report Set Entry, enter the RSE

object ID. To set a default value for a Parameter in the Execution Setup, enter the string you want to serve as the default value. The API returns the string.

Define Parameter Relations

This is a public interface for operations related to passing values from one Parameter to another within a Report Set or Workflow. For further information, see the chapter on Parameters in the *Oracle Life Sciences Data Hub Application Developer's Guide*.

This chapter contains the following procedures and functions:

- [Create a Parameter Relation Collection](#)
- [Get Parameter Instances for Value Passing](#)
- [Remove Parameter Relations](#)

Create a Parameter Relation Collection

Program instance contained in the Workflow and an input Parameter of another Program instance that is executed later in the Workflow.

Name

CDR_PUB_DF_PARAM_RELATION.CreateParrelColl

Signature

```
PROCEDURE CREATEPARRELCOLL(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_PARCOLL IN OUT CDR_PARAM_RELATION_COLL,
  PI_VALIDATERELATIONS IN VARCHAR := 'T'
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_PARCOLL** (Mandatory) This is a collection of CDR_PARAM_RELATION_OBJ_TYPES. For each Parameter relation that you want to create, initialize a CDR_PARAM_RELATION_OBJ_TYPE and then extend the collection. For the SRC attributes enter information about the Parameter whose value will be passed to another Parameter. For the TGT attributes, enter information about the target Parameter that will receive its value from the source Parameter. For RELATION_TYPE enter either LINK or SHARE.
- **PI_VALIDATERELATIONS** (Mandatory) Accept the default value of 'T' to validate the parameter relations in the collection. Enter 'F' to skip validation.

Get Parameter Instances for Value Passing

Use this API to get a list of Parameters that would be valid for either receiving a value from, or passing a value to, the Parameter you specify in the Report Set or Workflow you specify.

Name

CDR_PUB_DF_PARAM_RELATION.GetParameterRefs

Signature

```
PROCEDURE GETPARAMETERREFS( P_API_VERSION IN NUMBER, P_INIT_MSG_LIST IN
VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 :=
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER :=
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT VARCHAR2,
X_MSG_COUNT OUT NUMBER, X_MSG_DATA OUT VARCHAR2, PI_PSNSCOMPANYID IN
CDR_NAMINGS.COMPANY_ID%TYPE, PI_PSNSOBJID IN CDR_NAMINGS.OBJ_ID%TYPE,
PI_PSNSOBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE, PI_PAROBJID IN
CDR_NAMINGS.OBJ_ID%TYPE, PI_PAROBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE,
PO_PARCOLL OUT CDR_PARAM_RELATION_COLL, PI_SHARE IN VARCHAR2 );
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_PSNSCOMPANYID** (Mandatory) Enter the company ID of the Report Set or Workflow.
- **PI_PSNSOBJID** (Mandatory) Enter the object ID of the Report Set or Workflow.
- **PI_PSNSOBJVER** (Mandatory) Enter the version number of the Report Set or Workflow.
- **PI_PAROBJID** (Mandatory) Enter the object ID of the Parameter.
- **PI_PAROBJVER** (Mandatory) Enter the version number of the Parameter.
- **PO_PARCOLL** This output parameter is a collection of CDR_PARAM_RELATION_OBJ_TYPES containing Parameter instances in the Report Set or Workflow.
- **PI_SHARE** Enter SHAREDFROM to get a list of potential source Parameters that could pass their value to the Parameter you specified. Enter SHAREDTO to get a list of potential target Parameters that could receive their value from the Parameter you specified.

Remove Parameter Relations

Use this API to delete one or more Parameter relations from a Report Set or Workflow.

Name

CDR_PUB_DF_PARAM_RELATION.RemoveParrelColl

Signature

```
PROCEDURE REMOVEPARRELCOLL( P_API_VERSION IN NUMBER, P_INIT_MSG_LIST IN
VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 :=
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER :=
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT VARCHAR2,
X_MSG_COUNT OUT NUMBER, X_MSG_DATA OUT VARCHAR2, PIO_PARCOLL IN OUT
CDR_PARAM_RELATION_COLL );
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PIO_PARCOLL (Mandatory) This is a collection of CDR_PARAM_RELATION_OBJ_TYPES. For each Parameter relation that you want to delete, initialize a CDR_PARAM_RELATION_OBJ_TYPE and then extend the collection.

The following attributes are required: COMPANY_ID, SRC_PARENT_OBJ_ID, SRC_PARENT_OBJ_VER, SRC_PAR_REF_OBJ_ID, SRC_PAR_REF_OBJ_VER, TGT_PARENT_OBJ_ID, TGT_PARENT_OBJ_VER, TGT_PAR_REF_OBJ_ID, TGT_PAR_REF_OBJ_VER.

Variables

This is a public interface for Variable-related operations including creating, modifying, and removing Variables. It also includes functions for checking in and checking out Variables.

This chapter contains the following section:

- [Create and Modify Variables](#)

Create and Modify Variables

This section contains the following topics:

- [Create a Variable](#)
- [Check Out a Variable](#)
- [Modify a Variable](#)
- [Check In a Variable](#)
- [Remove a Variable](#)

Create a Variable

Use this API to create a new Variable instance.

Name

CDR_PUB_DF_VARIABLE.CreateVariable

Signature

```
PROCEDURE CREATEVARIABLE(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_NAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PIO_VARIABLE IN OUT CDR_VAR_OBJ_TYPE,
  PI_DEFCCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. For OBJECT_TYPE_RC enter \$OBJTYPES\$CDRVAR.

- PIO_VARIABLE** (Mandatory) This is a parameter of table type CDR_VAR_OBJ_TYPE that contains attributes specific to Variables.
 The required attributes are: ORACLE_NAME, ORACLE_DATATYPE_RC, LENGTH, PRECISION, SAS_V8_NAME, SAS_LABEL, SAS_FORMAT, NULLABLE_FLAG_RC, DEFAULT_VALUE.

 Possible values for ORACLE_DATATYPE_RC are: \$ORADATATYPES\$DATE, \$ORADATATYPES\$NUMBER, and \$ORADATATYPES\$VARCHAR2.

 Possible values for NULLABLE_FLAG_RC are: \$YESNO\$NO, \$YESNO\$YES.
- PI_DEFCLASSIFICATIONCOLL** By default, the variable is classified according to the subtype you assigned it in the CDR_NAMING_VERSION_OBJ_TYPE.
 If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID.

 If you want the definition to inherit its classifications for a particular level from its parent, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero).

 If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are not relevant to Variables. Do not enter any values for them.

 If you are not creating a new definition, do not enter values here.

Check Out a Variable

Use this API to check out a Variable definition or instance.

Name

CDR_PUB_DF_VARIABLE.CheckOut

Signature

```
PROCEDURE CHECKOUT (
  P_API_VERSION IN      NUMBER,
  P_INIT_MSG_LIST IN    VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN        VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN  NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT   VARCHAR2,
  X_MSG_COUNT OUT       NUMBER,
  X_MSG_DATA OUT        VARCHAR2,
  PIO_BASEOBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PI_COMMENT IN        VARCHAR2,
  PI_ISINSTONLY IN     VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Variable definition that you want to check out.
 The following attributes are required:
 COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.

- **PI_COMMENT** (Optional) Enter the reason you are checking out the Variable.
- **PI_ISINSTONLY** (Mandatory) Enter \$YESNO\$NO.

Modify a Variable

Use this API to modify a Variable definition or instance.



Note:

To modify a Variable definition, you must first check it out.

Name

CDR_PUB_DF_VARIABLE.ModifyVariable

Signature

```
PROCEDURE MODIFYVARIABLE(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_NAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PI_VARIABLE IN OUT CDR_VAR_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. Initialize the attributes COMPANY_ID, OBJECT_ID, and OBJECT_VER.
- **PI_VARIABLE** (Mandatory) This is a parameter of table type CDR_VARS_OBJ_TYPE. Provide values for the attributes you want to modify.

Check In a Variable

Use this API to check in a Variable definition or instance.

Name

CDR_PUB_DF_VARIABLE.CheckIn

Signature

```
PROCEDURE CHECKIN(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
```

```

X_MSG_DATA OUT    VARCHAR2,
PIO_BASEOBJECT IN OUT CDR_BASE_OBJ_TYPE,
PI_COMMENT IN     VARCHAR2
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Variable definition that you want to check in.
The following attributes are required:
COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.
- **PI_COMMENT** (Optional) Enter the reason you are checking in the Variable.

Remove a Variable

Use this API to remove an existing variable object.

Name

CDR_PUB_DF_VARIABLE.RemoveVariable

Signature

```

PROCEDURE REMOVEVARIABLE(
  P_API_VERSION IN    NUMBER,
  P_INIT_MSG_LIST IN  VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN       VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN  NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT   VARCHAR2,
  X_MSG_COUNT OUT      NUMBER,
  X_MSG_DATA OUT       VARCHAR2,
  PI_NAMING IN OUT     CDR_NAMING_VERSION_OBJ_TYPE
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

- **PI_NAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. Initialize the attributes COMPANY_ID, OBJECT_ID, and OBJECT_VER.

Work Areas

This is a public interface for Work Area-related operations, including creating, modifying, removing, cloning, checking in and installing Work Areas. It also includes an API to copy instance objects into a Work Area and an API to install a single Program.

- [Define and Modify Work Areas](#)

Define and Modify Work Areas

This section contains the following topics:

- [Create a Work Area](#)
- [Install a Work Area](#)
- [Check In a Work Area](#)
- [Modify a Work Area](#)
- [Clone a Work Area](#)
- [Copy Objects into a Work Area](#)
- [Clone an Object](#)
- [Remove a Work Area](#)
- [Get the Usage Intent RC of a Work Area](#)
- [Update a Work Area's Usage Intent](#)
- [Install a Program](#)
- [Apply or Move a Snapshot Label](#)
- [Remove a Snapshot Label from a Work Area](#)

Create a Work Area

Use this API to create a new Work Area.

Name

CDR_PUB_DF_WORKAREA.CreateWorkArea

Signature

```
PROCEDURE CREATEWORKAREA(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PIO_WORKAREAOBJTYPE IN OUT CDR_WORKAREA_OBJ_TYPE,
```

```
PI_DEFCCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_WORKAREAOBJTYPE** (Mandatory) This is a parameter of table type CDR_WORKAREA_OBJ_TYPE that contains object attributes specific to Work Areas. Enter values for the Work Area that you want to create.
The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER. For OBJECT_TYPE_RC enter \$OBJTYPES\$WORKAREA. By default, new Work Areas receive a Usage Intent value of Development.
- **PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Work Area that you want to create.
The following attributes are required:
COMPANY_ID, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_TYPE_RC.
FOR OBJECT_TYPE_RC ENTER \$OBJTYPES\$WORKAREA.
- **PI_DEFCCLASSIFICATIONCOLL** (Optional) By default the new Work Area is classified according to the subtype you assigned it in the CDR_NAMING_VERSION_OBJ_TYPE. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID. If you want the Work Area to inherit its classifications for a particular level from its parent Application Area, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero). If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are not relevant to Work Areas. Do not enter any values for them.

Install a Work Area

Use this API to install a Work Area and the instance objects in it that you specify. The API first tries to check in the Work Area and all the object instances included in the installation. If any object included in the installation is checked out by another user, the installation fails.

Name

CDR_PUB_DF_WORKAREA.InstallWAController

Signature

```
PROCEDURE INSTALLWACONTROLLER(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_OWABASENAMING IN OUT CDR_BASE_OBJ_TYPE,
  PI_VINSTALLMODE IN CDR_INSTALLATIONS.INSTALLATION_MODE_RC%TYPE,
  PI_VFORCEREGEN IN CDR_INSTALLATIONS.FORCE_REGEN_FLAG_RC%TYPE,
  PI_VBATCH IN CDR_INSTALLATIONS.BATCH_FLAG_RC%TYPE,
  PI_VACTION IN CDR_INST_ELEMENTS.INSTALL_ACTION_RC%TYPE,
  PI_COINSTDETAILS IN CDR_INSTALLATION_DETAILS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_OWABASENAMING** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Work Area that you want to install. The following attributes are required: COMPANY_ID,OBJECT_ID,OBJECT_VER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER, OBJECT_VERSION_NUMBER.
- **PI_VINSTALLMODE** (Mandatory) Specify the installation mode you want to use: Enter FULL, UPGRADE, or PARTIAL.
- **PI_VFORCEREGEN** (Optional) If you selected Upgrade mode, enter \$YESNO\$YES to force the system to generate new install scripts (and reinstall) all objects, whether or not they have been modified since the last installation of this Work Area. Enter \$YESNO\$NO to generate install scripts only for objects and object versions that have never been successfully installed.
- **PI_VBATCH** (Mandatory) Enter \$YESNO\$YES to perform installation in batch mode. Enter \$YESNO\$NO to perform installation in interactive mode.
- **PI_VACTION** (Mandatory) Enter COMPLETE if this is the first time the Work Area is being installed, or if the last installation was successful, or if the last installation failed and you want to continue from the last successfully completed phase. Enter CANCEL if the last installation failed and you want to begin the installation process from the beginning.
- **PI_COINSTDETAILS** (Mandatory) This is a collection of CDR_INST_DET_OBJ_TYPES. For each object in the Work Area that you want to install, initialize a CDR_INST_DET_OBJ_TYPE and then extend the collection. The following attributes are required: COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.

For OMIT_FROM_INSTALL_FLAG_RC, enter \$YESNO\$NO to include the object in the installation, subject to the rules for the installation type (Full, Partial, or Upgrade). If you are performing installation in PARTIAL mode, you must provide a value for each object for INSTALL_ACTION_RC of to indicate if you want to drop and replace or upgrade each object.

Check In a Work Area

Use this API to check in a Work Area and all the object instances it contains.

Name

CDR_PUB_DF_WORKAREA.CheckInWorkArea

Signature

```

PROCEDURE CHECKINWORKAREA(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_BASENAMING IN OUT CDR_BASE_OBJ_TYPE,

```

```
PI_COMMENT IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_BASENAMING** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Work Area that you want to check in. The following attributes are required: COMPANY_ID, OBJECT_ID, OBJECT_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_VERSION_NUMBER.
- **PI_COMMENT** (Optional) Enter the reason you are checking in the Work Area.

Modify a Work Area

Use this API to modify the name and/or description of an existing Work Area. (Use CDR_PUB_DF_WORKAREA.UPDATEUSAGEINTENT to modify a Work Area's Usage Intent attribute.)

Name

CDR_PUB_DF_WORKAREA.ModifyWorkArea

Signature

```
PROCEDURE MODIFYWORKAREA(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PIO_WORKAREAOBJTYPE IN OUT CDR_WORKAREA_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Work Area that you want to modify and the values you want to change. All attributes are required.
- **PIO_WORKAREAOBJTYPE** (Mandatory) This is a parameter of table type CDR_WORKAREA_OBJ_TYPE that contains object attributes specific to Work Areas. Enter values to identify the Work Area that you want to modify and enter new values for the attributes you want to modify.

Clone a Work Area

Use this API to clone a Work Area. If you specify another Work Area as the target, this API overwrites that Work Area with the source Work Area. If you specify an Application Area as the target, this API creates a new Work Area identical to the source Work Area in the Application Area you specify.

Name

CDR_PUB_DF_WORKAREA.CloneWorkArea

Signature

```
PROCEDURE CLONEWORKAREA(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCEOBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PIO_TARGETOBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PI_VLABEL IN CDR_WORKAREAS.LABEL%TYPE,
  PI_VUSAGEINTENTRC IN CDR_WORKAREAS.USAGE_INTENT_RC%TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SOURCEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Work Area that you want to clone. The following attributes are required: COMPANY_ID, OBJECT_ID, OBJECT_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_VERSION_NUMBER.
- **PIO_TARGETOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Work Area or Application Area to serve as the target of the clone. If you specify a Work Area, this API overwrites it with the source Work Area. If you specify an Application Area, this API creates a new Work Area identical to the source Work Area in the Application Area. The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.
- **PI_VLABEL** (Mandatory) Enter text for the label you want to assign to the source and target Work Areas.
- **PI_VUSAGEINTENTRC** (Optional) Enter a value for the Usage Intent attribute of the target Work Area. If you do not enter a value, the API assigns the Usage Intent value of the source Work Area to the target Work Area.

Copy Objects into a Work Area

Use this API to copy one or more objects into a Work Area.

Name

CDR_PUB_DF_WORKAREA.CopyObjectsIntoWA

Signature

```
PROCEDURE COPYOBJECTSINTOWA(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
```

```

X_MSG_COUNT OUT NUMBER,
X_MSG_DATA OUT VARCHAR2,
PI_CDRPRREFOBJCOLL IN CDR_PRREF_OBJ_COLL,
PI_CDRTARGETCONTAINEROBJECT IN OUT CDR_PRREF_OBJ_TYPE,
PI_CHECKINFLAG IN VARCHAR,
PI_COPYPRGASSGNMT IN VARCHAR
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_CDRPRREFOBJCOLL** (Mandatory) This is a collection of Prref objects that contains information about the instance objects you want to copy into the Work Area. Provide values for the attributes COMPANY_ID, OBJ_ID, OBJ_VER, PRREF_ID, PRREF_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_VERSION_NUMBER for each instance object. The PRREF_ID and PRREF_VER attributes store the hierarchy information for objects.
- **PI_CDRTARGETCONTAINEROBJECT** (Mandatory) This is a parameter of Prref object type that describes the target Work Area. Enter values for the attributes COMPANY_ID, OBJ_ID, OBJ_VER, PRREF_ID, PRREF_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_VERSION_NUMBER.
- **PI_CHECKINFLAG** (Mandatory) Enter 'Y' for this flag.
- **PI_COPYPRGASSGNMT** (Optional) This parameter is not applicable.

Clone an Object

Use this API to clone one or more instance objects in a Work Area.

Name

CDR_PUB_DF_WORKAREA.CloneObjects

Signature

```

PROCEDURE CLONEOBJECTS(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_SRCINSTBASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL,
  PI_TGTWABASEOBJTYPE IN OUT CDR_BASE_OBJ_TYPE
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_SRCINSTBASEOBJCOLL** (Mandatory) This is a collection of base objects that you want to clone in the Work Area. Enter the attributes COMPANY_ID, OBJ_ID, OBJ_VER, PRREF_ID, PRREF_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_VERSION_NUMBER for each instance object.

- **PI_TGTWABASEOBJTYPE** (Mandatory) This is a parameter of base object type that describes the Work Area.
Enter the Work Area's COMPANY_ID, OBJ_ID, OBJ_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_VERSION_NUMBER.

Remove a Work Area

Use this API to remove a Work Area and all the instance objects it contains.

Name

CDR_PUB_DF_WORKAREA.RemoveWorkArea

Signature

```
PROCEDURE REMOVEWORKAREA(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PIO_SOURCECDRNAMING (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Work Area that you want to remove. The following attributes are required:
COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.

Get the Usage Intent RC of a Work Area

Use this API to retrieve the current value of the Usage Intent attribute for a particular Work Area.

Name

CDR_PUB_DF_WORKAREA.GetUsageIntentRC

Signature

```
PROCEDURE GETUSAGEINTENTRC(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_COMPANY_ID IN CDR_NAMINGS.COMPANY_ID%TYPE,
  PI_OBJ_ID IN CDR_NAMINGS.OBJ_ID%TYPE,
  PI_OBJ_VER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE,
  PO_USAGEINTENT OUT CDR_WORKAREAS.USAGE_INTENT_RC%TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPANY_ID** (Mandatory) Enter company ID
- **PI_OBJ_ID** (Mandatory) Enter the object ID of the Work Area.
- **PI_OBJ_VER** (Mandatory) Enter the object version (OBJ_VER) of the Work Area.
- **PO_USAGEINTENT** This output parameter returns the current value of the Work Area's Usage Intent attribute.

Update a Work Area's Usage Intent

Use this API to modify the value of the Usage Intent attribute of a Work Area.

Name

CDR_PUB_DF_WORKAREA.UpdateUsageIntent

Signature

```
PROCEDURE UPDATEUSAGEINTENT (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PIO_WORKAREAOBJTYPE IN OUT CDR_WORKAREA_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Work Area whose Usage Intent attribute you want to modify.
The following attributes are required: COMPANY_ID,OBJ_ID,OBJ_VER.
- **PIO_WORKAREAOBJTYPE** (Mandatory) This is a parameter of table type CDR_WORKAREA_OBJ_TYPE that contains object attributes specific to Work Areas. For USAGE_INTENT_RC, enter the new value for the Usage Intent attribute.
The allowed values are: \$SYSVALDNSTEPS\$DEVELOPMENT, \$SYSVALDNSTEPS\$PRODUCTION, \$SYSVALDNSTEPS\$QUALITYCONTROL.

Install a Program

Use this API to install a single Program and the Table instances to which it is mapped. You must install a Program and its source Table instances before you can work on it in an Integrated Development Environment (IDE).

Name

CDR_PUB_DF_WORKAREA.InstallIDEcomponents

Signature

```
PROCEDURE INSTALLIDECOMPONENTS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_NCOMPANYID IN NUMBER,
  PI_NWAOBJID IN NUMBER,
  PI_NWAOBJVER IN NUMBER,
  PI_NPRREFID IN NUMBER,
  PI_NPRREFVER IN NUMBER,
  PO_VINSTLOGTYPE OUT VARCHAR2,
  PO_VINSTLOG OUT VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NCOMPANYID** (Mandatory) Enter your company ID. To get your company ID, use CDR_PUB_DEF_FACTORY_UTILS.GetCompanyId.
- **PI_NWAOBJID** (Mandatory) Enter the object ID of the Work Area where the Program instance is located.
- **PI_NWAOBJVER** (Mandatory) Enter the object version (OBJ_VER) of the Work Area.
- **PI_NPRREFID** (Mandatory) Enter the object ID of the Program instance that you want to install.
- **PI_NPRREFVER** PrrefVer of the Program Instance to be installed
- **PO_VINSTLOGTYPE** This output parameter returns one of the following values to indicate whether the installation ended with a status of Warning (G_RET_IDE_INST_WARNING) or Success (G_RET_IDE_INST_INFO).
- **PO_VINSTLOG** This output parameter returns the installation log file (maximum length 32000 characters).

Apply or Move a Snapshot Label

Use this API to apply a snapshot label to some or all tables and/or views in a Work Area.

Name

CDR_PUB_EXE_SNAPSHOT.SetOrMoveLabel

Signature

```
PROCEDURE SETORMOVELABEL (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PI_WA_COMPANY_ID IN CDR_NAMINGS.COMPANY_ID%TYPE,
  PI_WA_OBJ_ID IN CDR_NAMINGS.OBJ_ID%TYPE,
  PI_WA_OBJ_VER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE,
  PI_LABEL IN CDR_TAB_REF_LABELS.LABEL%TYPE,
```

```

PI_FORCE_FLAG          IN CDR_SUBMISSIONS.FORCE_EXECUTION_FLAG_RC%TYPE,
PI_BLIND_FLAG IN CDR_TABLE_REF_JOBS.BLIND_BREAK_FLAG_RC%TYPE,
PI_DATE IN DATE DEFAULT NULL,
PI_SRC_TAB_COLL CDR_SRC_TABLE_COLL DEFAULT NULL,
PI_WA_TABLES_COLL IN OUT NOCOPY CDR_WA_TABLES_COLL,
X_MSG_COUNT OUT NUMBER,
X_MSG_DATA OUT VARCHAR2,
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters. See [Functional Rules](#) below for more information.

- **PI_WA_COMPANY_ID** (Mandatory) Enter the Company ID.
- **PI_WA_OBJ_ID** (Mandatory) Enter the Work Area object ID.
- **PI_WA_OBJ_VER** (Mandatory) Enter the latest object version.
- **PI_LABEL** (Mandatory) Label text.
- **PI_FORCEFLAG** (Mandatory)
 - If set to **\$YESNO\$YES**, the API overwrites the previous snapshot label.
 - If set to **\$YESNO\$NO** the label is not applied.
- **PI_BLIND_FLAG** (Mandatory) The Blind Break flag (\$YESNO\$YES, \$YESNO\$NO).
- **PI_DATE** (Optional) If this value is used, the API labels only those tables with latest data loads less than or equal to entered value.
- **PI_SCR_TAB_COLL** (Optional) Naming details of source table(s) of view in given Work Area and corresponding view naming details (to match value with CDR_WA_TABLES_COLL).
This parameter is of type CDR_SRC_TABLE_OBJ_TYPE and contains the following naming attributes:
 - **SRC_TI_COMPANY_ID NUMBER(6)** Enter the Table or view Company ID.
 - **SRC_TI_OBJ_ID NUMBER(22)** Enter the Table or view object ID.
 - **SRC_TI_OBJ_VER NUMBER(7)** Enter the Table or view object version.
 - **SRC_TI_LABEL VARCHAR2(4000)** Source table's already applied label to any given load.
 - **VW_TI_COMPANY_ID NUMBER(6)** Enter the view Company ID.
 - **VW_TI_OBJ_ID NUMBER(22)** Enter the view object ID.
 - **VW_TI_OBJ_VER NUMBER(7)** Enter the view object version.
- **PI_WA_TABLES_COLL** (Optional) This is a parameter of type CDR_WA_TABLES_TYPE that contains table naming attributes.
Use this parameter if the API call is intended to set the label for only a subset of table(s) of an Work Area. It contains following naming attributes:
 - **TI_COMPANY_ID NUMBER(6)** Table COMPANY_ID to which label need to be set.
 - **TI_OBJ_ID NUMBER(22)** Enter the object ID for the Table for which the label needs to be set.
 - **TI_OBJ_VER NUMBER(7)** Enter the object version for the Table for which the label needs to be set.
 - **TI_RET_STATUS VARCHAR2(4000)** This is return status, should be passed as null.

Functional Rules

The following rules outline the API's behavior depending on parameter usage in the API call:

- If PI_WA_TABLES_COLL is used, it will apply the label only to the entered table(s) and/or view(s).
- If PI_WA_TABLES_COLL is null, the label is applied to all table(s)/view(s) in the Work Area.
- Multiple labels cannot be applied to the same table/view in one API call.
- If PI_DATE is used, the label is applied to the latest Table data load, less than equals to the used date.
- If PI_DATE is not used, the label is applied to latest Table data load.
- If PI_FORCEFLAG is set to **\$YESNO\$YES**, the API overwrites the Snapshot Label if already applied, otherwise the label is not applied.
- If PI_FORCEFLAG is set to **\$YESNO\$YES**, non-blinded Tables are always included to be labeled.
- If PI_SRC_TAB_COLL is null, and PI_WA_TABLES_COLL has view information or is null (if view exists), the view is loaded and labeled with latest loaded data from the source table.
- If PI_SRC_TAB_COLL has a partial set of source table or views, and PI_WA_TABLES_COLL has view information, the view is loaded and labeled with the latest loaded data from the source table that has non-passed source information.
- If PI_SRC_TAB_COLL is used, the view details should be part of PI_WA_TABLES_COLL.
- If PI_SRC_TAB_COLL is null label will be applied to all table(s) in given Work Area.
- If collection PI_SRC_TAB_COLL is passed with source table's label then view will be loaded and labeled with that data of source table.
- If PI_SRC_TAB_COLL is used with the source table's label as null, then the view is loaded and labeled with latest loaded data of source table.

Remove a Snapshot Label from a Work Area

Use this API to remove a snapshot label from the passing Work Area.

Name

CDR_PUB_EXE_SNAPSHOT.RemoveLabel

Signature

```

PROCEDURE REMOVELABEL (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PI_WA_COMPANY_ID IN CDR_NAMINGS.COMPANY_ID%TYPE,
  PI_WA_OBJ_ID IN CDR_NAMINGS.OBJ_ID%TYPE,
  PI_WA_OBJ_VER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE,
  PI_WA_TABLES_COLL in OUT NOCOPY CDR_WA_TABLES_COLL,
  PI_LABEL IN CDR_TAB_REF_LABELS.LABEL%TYPE,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,

```

```
X_MSG_DATA OUT VARCHAR2,  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

- **PI_WA_COMPANY_ID** (Mandatory) Enter the Company ID.
- **PI_WA_OBJ_ID** (Mandatory) Enter the Work Area object ID.
- **PI_WA_OBJ_VER** (Mandatory) Enter the latest object version.
- **PI_WA_TABLES_COLL** (Optional) User can pass the collection of table instance of the same Work Area on which user want remove the Snapshot Label.
- **PI_LABEL** (Mandatory) Label value.

Workflows

This is a public interface for Workflow-related operations, including creating, modifying, and removing Workflows.

This chapter contains the following section:

- [Create and Modify Workflows](#)

Create and Modify Workflows

This section contains the following topics:

- [Create a Workflow](#)
- [Check Out a Workflow Definition](#)
- [Create a Workflow Transition](#)
- [Create a Workflow Structure Instance](#)
- [Modify a Workflow](#)
- [Modify a Workflow](#)
- [Check In a Workflow Definition](#)
- [Remove a Transition](#)
- [Remove a Workflow Activity](#)
- [Remove a Workflow Instance](#)
- [Remove a Workflow Definition](#)

Create a Workflow

Use this API to create a Workflow definition or instance.

Name

CDR_PUB_DF_WORKFLOW.CreateWorkFlow

Signature

```
PROCEDURE CREATEWORKFLOW(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PI_CREATEOBJECT IN VARCHAR2,
  PI_INSTANCE_SUBTYPE_ID IN CDR_NAMINGS.OBJECT_SUBTYPE_ID%TYPE,
  PI_DEFCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL,
```

```
PI_INSTCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. For OBJECT_TYPE_RC enter \$OBJTYPES\$WORKFLOW if you are creating a definition only; \$OBJTYPES\$WORKFLOWREF if you are creating an instance of an existing definition; and also if you are creating a new definition and an instance of it.

- **PI_CREATEOBJECT** (Mandatory) Enter DEFN to create a definition only; INST to create an instance of an existing definition; or BOTH to create a new definition and an instance of it.

Valid parameters are: Definition—DEFN, instance—INST, both —BOTH.

- **PI_INSTANCE_SUBTYPE_ID** (Optional) If you are creating a new instance, enter the ID for the subtype you want to give the instance. If you are creating a definition only, do not enter a value for this parameter.

- **PI_DEFCLASSIFICATIONCOLL** (Optional) By default the new definition is classified according to the subtype you assigned it in the CDR_NAMING_VERSION_OBJ_TYPE. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID.

If you want the definition to inherit its classifications for a particular level from its parent, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero). If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are not relevant to Workflow definitions. Do not enter any values for them.

- **PI_INSTCLASSIFICATIONCOLL** (Optional) By default the new instance is classified according to the subtype you assigned it in the PI_INSTANCE_SUBTYPE_ID. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID.

If you want the instance to inherit its classifications for a particular level from its parent Work Area, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are not relevant to Workflows. Do not enter any values for them. If you are not creating a new instance, do not enter values here.

Check Out a Workflow Definition

Use this API to check out a Workflow definition.

Name

CDR_PUB_DF_WORKFLOW.CheckOutWorkflow

Signature

```
PROCEDURE CHECKOUTWORKFLOW(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_CDRWORKFLOW IN OUT CDR_BASE_OBJ_TYPE,
  PI_COMMENT IN VARCHAR2,
  PI_ISINSTONLY IN VARCHAR2,
  PI_OPTYPE IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_CDRWORKFLOW** [Mandatory] This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Workflow definition that you want to check in.
The following attributes are mandatory: COMPANY_ID, OBJECT_ID, OBJECT_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_VERSION_NUMBER. Initialize these attributes in CDR_BASE_OBJ_TYPE.
- **PI_COMMENT** [Optional] Enter the reason for checking out the Workflow definition.
- **PI_ISINSTONLY** (Mandatory) Enter \$YESNO\$NO. (The \$YESNO\$YES setting is used internally only.)
- **PI_OPTYPE** (Mandatory) Enter NULL for this parameter.

Create a Workflow Transition

Use this API to create a Workflow transition. A Workflow transition connects two Workflow activities.

Name

CDR_PUB_DF_WORKFLOW.CreateWfTransition

Signature

```
PROCEDURE CREATEWFTRANSITION(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PI_CDRWFTRANSITION IN OUT CDR_WMG_TRANS_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. For OBJECT_TYPE_RC enter \$OBJTYPES\$WORKFLOW if you are creating a definition only; \$OBJTYPES\$WORKFLOWREF if you are creating an instance of an existing definition; and also if you are creating a new definition and an instance of it.
- **PI_CDRWFTRANSITION** The Object ID and Version of the two Workflow activities being connected through this transition should be populated in the CDR_WMG_TRANS_OBJ_TYPE. In the CONDITION_RC attribute, specify the activity condition based on which the workflow transitions to the other specified activity.

The possible values are \$WFTRANSITIONS\$NONE, \$WFTRANSITIONS\$SUCCESS, \$WFTRANSITIONS\$ERROR, \$WFTRANSITIONS\$WARNING

Create a Workflow Structure Instance

Use this API to create a Workflow Structure. These are the Workflow structures: And, Or, Start, End_Success, End_Warning, End_Error, and Fork.

Name

CDR_PUB_DF_WORKFLOW.CreateWfStructref

Signature

```
PROCEDURE CREATEWFSTRUCTREF (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_SOURCECDRNAMING (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes.

For OBJECT_TYPE_RC enter \$OBJTYPES\$WORKFLOW if you are creating a definition only; \$OBJTYPES\$WORKFLOWREF if you are creating an instance of an existing definition; and also if you are creating a new definition and an instance of it.

Modify a Workflow

Name

CDR_PUB_DF_WORKFLOW.ModifyWorkflow

Signature

```
PROCEDURE MODIFYWORKFLOW (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
```

```

P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT VARCHAR2,
X_MSG_COUNT OUT NUMBER,
X_MSG_DATA OUT VARCHAR2,
PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PIO_SOURCECDRNAMING (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes.

For OBJECT_TYPE_RC enter \$OBJTYPES\$WORKFLOW if you are creating a definition only; \$OBJTYPES\$WORKFLOWREF if you are creating an instance of an existing definition; and also if you are creating a new definition and an instance of it.

Modify a Workflow

Use this API to reorder workflow transitions.

Name

CDR_PUB_DF_WORKFLOW.ReorderWfTransitions

Signature

```

PROCEDURE REORDERWFTRANSITIONS(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_REORDEROBJCOLL IN CDR_REORDER_OBJ_COLL
);

```

Parameters

This API has standard parameters (see ["Standard Parameters"](#)) and the following parameter:

PI_REORDEROBJCOLL Collection of the columns to be re-ordered.

Check In a Workflow Definition

Use this API to check in a Workflow definition object.

Name

CDR_PUB_DF_WORKFLOW.CheckInWorkFlowDef

Signature

```

PROCEDURE CHECKINWORKFLOWDEF(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,

```

```

P_VALIDATION_LEVEL IN    NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS   OUT    VARCHAR2,
X_MSG_COUNT       OUT    NUMBER,
X_MSG_DATA        OUT    VARCHAR2,
PIO_CDRWORKFLOW   IN OUT  CDR_BASE_OBJ_TYPE,
PI_COMMENT        IN     VARCHAR2
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_CDRWORKFLOW** This parameter refers to the workflow definition to be checked in. Initialize in `cdr_base_obj_type`, the basic naming details (COMPANY_ID, OBJ_ID, OBJ_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_VERSION_NUMBER) of the workflow to be checked in.
- **PI_COMMENT** Comment to be associated with the check in operation

Remove a Transition

Use this API to remove one or more Workflow transitions.

Name

CDR_PUB_DF_WORKFLOW.RemoveWfTransition

Signature

```

PROCEDURE REMOVEWFTRANSITION(
  P_API_VERSION IN    NUMBER,
  P_INIT_MSG_LIST IN   VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN        VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN    NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS   OUT    VARCHAR2,
  X_MSG_COUNT       OUT    NUMBER,
  X_MSG_DATA        OUT    VARCHAR2,
  PI_CDRCHILD OBJS IN     CDR_BASE_OBJ_COLL
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_CDRCHILD OBJS (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES.

For each Workflow transition that you want to remove, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.

The following attributes are required for each Workflow transition: COMPANY_ID, OBJ_ID, OBJ_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_VERSION_NUMBER.

Remove a Workflow Activity

Use this API to remove one or more Workflow activities. Workflow activities include all executable objects: Load Sets, Programs, Data Marts, and Report Sets; and also Workflow structures: And, Or, Start, End_Success, End_Warning, End_Error, and Fork.

Name

CDR_PUB_DF_WORKFLOW.RemoveObjectsFromWorkflow

Signature

```
PROCEDURE REMOVEOBJECTSFROMWORKFLOW (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_CDRCHILD OBJS IN CDR_BASE_OBJ_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_CDRCHILD OBJS (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES.

For each Workflow activity that you want to remove, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.

The following attributes are required for each Workflow activity: COMPANY_ID, OBJ_ID, OBJ_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_VERSION_NUMBER.

Remove a Workflow Instance

Use this API to remove a Workflow instance object.

Name

CDR_PUB_DF_WORKFLOW.Remove

Signature

```
PROCEDURE REMOVE (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_BASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_BASEOBJCOLL This refers to collection of workflow instances to be removed.

Remove a Workflow Definition

Use this API to remove one or more Workflow definitions.

Name

CDR_PUB_DF_WORKFLOW.RemoveWorkFlow

Signature

```
PROCEDURE REMOVEWORKFLOW(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  X_RETURN_STATUS OUT VARCHAR2,  
  X_MSG_COUNT OUT NUMBER,  
  X_MSG_DATA OUT VARCHAR2,  
  PIO_CDRWORKFLOW IN OUT CDR_BASE_OBJ_TYPE  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_CDRWORKFLOW (Mandatory) This is a parameter of CDR_BASE_OBJ_TYPES.

For each Workflow that you want to remove, initialize a CDR_BASE_OBJ_TYPE.

The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_VERSION_NUMBER of the workflow to be removed should be initialized in cdr_base_obj_type.

Workflow Notifications

This is a public interface for Notifications-related operations.

This chapter contains the following section:

- [Create and Modify Notifications](#)

Create and Modify Notifications

This section contains the following topics:

- [Create a Notification](#)
- [Create a Notification Recipient](#)
- [Create a Notification Link](#)
- [Check Out a Notification Definition](#)
- [Modify a Notification Definition](#)
- [Modify a Notification Instance](#)
- [Send a Notification](#)
- [Check In a Notification Definition](#)
- [Remove a Notification Link](#)
- [Remove a Notification Recipient](#)
- [Remove a Notification](#)

Create a Notification

Use this API to create a Notification definition or instance. This API also initializes the classification of the new Notification object.

Name

CDR_PUB_DF_NOTIFICATIONS.CreateNotification

Signature

```
PROCEDURE CREATENOTIFICATION(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PI_CDRNOTIFICATION IN CDR_NOTIFICATION_OBJ_TYPE,
  PI_CREATEOBJECT IN VARCHAR2,
```

```
PI_DEFCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. If you are creating a new definition only or a new definition and an instance of it, enter values for the new definition.

If you are creating an instance of an existing definition, enter values to identify the existing definition.

For OBJECT_TYPE_RC enter \$OBJTYPES\$NOTIFICATION if you are creating a definition only; \$OBJTYPES\$NOTIFREF if you are creating an instance of an existing definition; and also if you are creating a new definition and an instance of it.
- PI_CDRNOTIFICATION** (Mandatory) This is a parameter of table type CDR_NOTIFICATION_OBJ_TYPE that contains Notification specific attributes. Enter FYI or APPROVAL for NOTIF_TYPE_RC.

Enter HIGH, MEDIUM, or LOW for NOTIF_PRIORITY_RC.

Enter ALL or ANY for ALL_REPLIES_FLAG_RC for Notifications of type APPROVAL.
- PI_CREATEOBJECT** Enter DEFN for creating a definition, INST for creating an instance, and BOTH for creating a definition and an instance of it.
- PI_DEFCLASSIFICATIONCOLL** (Optional) By default the new definition is classified according to the subtype you assigned it in the CDR_NAMING_VERSION_OBJ_TYPE. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID.

If you want the definition to inherit its classifications for a particular level from its parent, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID.

The PAR_ attributes are not relevant to Notifications. Do not enter any values for them.

Create a Notification Recipient

Use this API to create Notification recipients. Notification recipients are group roles of a user group.

Name

CDR_PUB_DF_NOTIFICATIONS.CreateNotificationRecipient

Signature

```
PROCEDURE CREATENOTIFICATIONRECIPIENT(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
```

```

X_MSG_DATA OUT VARCHAR2,
PI_CDRNOTIFRECIPIENTS IN CDR_NTFRCP_COLL
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_CDRNOTIFRECIPIENTS This is a collection of CDR_NOTIF_RECIPIENT_OBJ_TYPE.

If the Notification is of type APPROVAL, for the attribute FALLBACK_FLAG_RC you need to enter \$NOTIFRCPTTYPE\$PRIMARY if the recipient is Primary or \$NOTIFRCPTTYPE\$BACKUP if the recipient is Backup.

If the Primary recipients do not respond to an APPROVAL type of Notification within the defined time frame, then the Notification is sent to the Backup recipients.

Create a Notification Link

Use this API to create links to Planned Outputs of executables owned by a Workflow.

Name

CDR_PUB_DF_NOTIFICATIONS.CreateNotificationLinks

Signature

```

PROCEDURE CREATENOTIFICATIONLINKS(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_CDRNOTIFLINKS IN CDR_NOTIF_LINKS_OBJ_COLL
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PI_CDRNOTIFLINKS This is a collection of CDR_NOTIF_LINKS_OBJ_TYPE.

You need to enter values for the following attributes: COMPANY_ID, NFINST_OBJ_ID, NFINST_OBJ_VER, PO_COMPANY_ID, PO_OBJ_ID, ACTIVITY_COMPANY_ID, ACTIVITY_OBJ_ID, ACTIVITY_OBJ_VER.

Check Out a Notification Definition

Use this API to check out a Notification definition.

Name

CDR_PUB_DF_NOTIFICATIONS.CheckOutNotif

Signature

```

PROCEDURE CHECKOUTNOTIF(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,

```

```

P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT VARCHAR2,
X_MSG_COUNT OUT NUMBER,
X_MSG_DATA OUT VARCHAR2,
PIO_CDRNOTIF IN OUT CDR_BASE_OBJ_TYPE,
PI_COMMENT IN VARCHAR2,
PI_ISINSTONLY IN VARCHAR2,
PI_OPTYPE IN VARCHAR2
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_CDRNOTIF** [Mandatory] This is a parameter of table type CDR_BASE_OBJ_TYPE. Identify the Notification definition you want to check out. Provide the basic naming attributes: COMPANY_ID, OBJECT_ID, OBJECT_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_VERSION_NUMBER. Initialize these attributes in CDR_BASE_OBJ_TYPE.
- **PI_COMMENT** (Optional) Enter the reason you are checking in the Notification.
- **PI_ISINSTONLY** Enter \$YES\$NO\$NO.
- **PI_OPTYPE** Enter NULL for this parameter.

Modify a Notification Definition

Use this API to modify a Notification definition. You need to check out the Notification definition first.

Name

CDR_PUB_DF_NOTIFICATIONS.ModifyNotification

Signature

```

PROCEDURE MODIFYNOTIFICATION(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PI_CDRNOTIFICATION IN CDR_NOTIFICATION_OBJ_TYPE
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. Initialize the attributes COMPANY_ID, OBJECT_ID, and OBJECT_VER.
- **PI_CDRNOTIFICATION** (Mandatory) This is a parameter of table type CDR_NOTIFICATION_OBJ_TYPE. Provide values for the attributes you want to modify.

Modify a Notification Instance

Use this API to modify a Notification instance.

Name

CDR_PUB_DF_NOTIFICATIONS.ModifyNotificationInstance

Signature

```
PROCEDURE MODIFYNOTIFICATIONINSTANCE(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PI_CDRNOTIFICATION IN CDR_NOTIFICATION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. Initialize the attributes COMPANY_ID, OBJECT_ID, and OBJECT_VER.
- **PI_CDRNOTIFICATION** (Mandatory) This is a parameter of table type CDR_NOTIFICATION_OBJ_TYPE. Provide values for the attributes you want to modify.

Send a Notification

Use this API to send an information Notification either from a Program or from another database user.

Name

CDR_PUB_DF_NOTIFICATIONS.Send_FYI_Notification

Signature

```
PROCEDURE SEND_FYI_NOTIFICATION
  PI_JOB_ID NUMBER IN PI_USER GROUP
  VARCHAR2 IN PI_ROLE_CODE VARCHAR2 IN
  PI_SUBJECT VARCHAR2 IN PI_BODY
  VARCHAR2 IN PI_URL VARCHAR2 IN
  PI_URLNAME VARCHAR2 IN DEFAULT
  PI_CDRNOTIFLINKS CDR_NOTIF_LINKS_OBJ_COLL IN DEFAULT,
);
```

If the user wants to include just one URL in the notification, it can be passed in pi_url and the string to be shown for the hyperlink should be passed in pi_urlName.

On the other hand if the user wants to include links to some or all of the outputs generated by the job, then the list of the corresponding planned output IDs should be passed in the last collection parameter.

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_JOB_ID** Enter the job ID created for the corresponding job for the notifications sent.
- **PI_USER_GROUP** Enter the user group identifier.
- **PI_ROLE_CODE** Enter the role code identifier.
- **PI_SUBJECT** Enter the subject of the notification.
- **PI_BODY** Enter the body content of the notification.
- **PI_URL** Enter the URL to be embedded in the notification.

Check In a Notification Definition

Use this API to check in a Notification definition.

Name

CDR_PUB_DF_NOTIFICATIONS.CheckInNotifDef

Signature

```
PROCEDURE CHECKINNOTIFDEF(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_CDRNOTIF IN OUT CDR_BASE_OBJ_TYPE,
  PI_COMMENT IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_CDRNOTIF** [Mandatory] This is a parameter of table type CDR_BASE_OBJ_TYPE that object attributes.
Identify the Notification definition you want to check in. Provide the basic naming attributes: COMPANY_ID, OBJECT_ID, OBJECT_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_VERSION_NUMBER. Initialize these attributes in CDR_BASE_OBJ_TYPE.
- **PI_COMMENT** (Optional) Enter the reason you are checking in the Notification.

Remove a Notification Link

Use this API to remove links to Planned Outputs of executables owned by the Workflow.

Name

CDR_PUB_DF_NOTIFICATIONS.RemoveNotificationLinks

Signature

```
PROCEDURE REMOVENOTIFICATIONLINKS (
  P_API_VERSION IN    NUMBER,
  P_INIT_MSG_LIST IN   VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN         VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN  NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT   VARCHAR2,
  X_MSG_COUNT OUT      NUMBER,
  X_MSG_DATA OUT       VARCHAR2,
  PI_CDRNOTIFLINKS IN   CDR_NOTIF_LINKS_OBJ_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_CDRNOTIFLINKS (Mandatory) This is a collection of CDR_NOTIF_LINKS_OBJ_TYPE. For each Planned Output link that you want to remove, initialize a CDR_NOTIF_LINKS_OBJ_TYPE and then extend the collection.

Remove a Notification Recipient

Use this API to remove a Notification recipient.

Name

CDR_PUB_DF_NOTIFICATIONS.RemoveNotificationRecipients

Signature

```
PROCEDURE REMOVENOTIFICATIONRECIPIENTS (
  P_API_VERSION IN    NUMBER,
  P_INIT_MSG_LIST IN   VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN         VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN  NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT   VARCHAR2,
  X_MSG_COUNT OUT      NUMBER,
  X_MSG_DATA OUT       VARCHAR2,
  PI_CDRNOTIFRECIPIENTS IN  CDR_NTFRCP_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PI_CDRNOTIFRECIPIENTS This is a collection of CDR_NOTIF_RECIPIENT_OBJ_TYPE.

For each Recipient that you want to remove, initialize a CDR_NOTIF_RECIPIENT_OBJ_TYPE and then extend the collection.

The following attributes are required:

COMPANY_ID,OBJ_ID,OBJ_VER,USER_GROUP_ID,ROLE_ID,FALLBACK_FLAG_RC.

Remove a Notification

Use this API to remove a Notification definition.

Name

CDR_PUB_DF_NOTIFICATIONS.RemoveNotifications

Signature

```
PROCEDURE REMOVENOTIFICATIONS(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_BASEOBJCOLL IN OUT CDR_BASE_OBJ_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_BASEOBJCOLL (Mandatory) This is a collection of CDR_BASE_OBJ_TYPE. For each Notification that you want to remove, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.

The following attributes are required:

COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

Part III

Common APIs

This part of the Oracle Life Sciences Warehouse API guide contains APIs that you can use to perform common tasks required for many different object types.

Part III contains the following chapters:

- [Setup Utilities](#)
- [Execution Setups](#)
- [Mappings](#)
- [Outputs](#)
- [Version Labels](#)
- [Classification](#)
- [Job Execution](#)
- [Security Policy](#)
- [Validation](#)

Setup Utilities

This is a public interface for operations related to the setting up of utilities in Oracle LSH.

This section contains the following topics:

- [Initialize APIs](#)
- [Get Factory Support](#)
- [Get Factory Utilities](#)
- [Get Factory Validations](#)
- [Get Data from Object Naming Tables](#)
- [Define and Modify Adapters](#)
- [Host Definition Constants](#)
- [Read Messages](#)
- [Change Tablespaces](#)

Initialize APIs

This is a public interface that is used internally to initialize all other Oracle LSH external API packages. See [Calling the Security API Package](#) for details. See [Code Example Using Security and Error Message APIs](#) for an example of a program that calls the initialization API.

This section contains the following topics:

- [Initialize a Package](#)
- [Verify Whether an API is Enabled](#)
- [Enable an API](#)
- [Disable an API](#)

Initialize a Package

This is used internally to initialize external Oracle LSH API packages.

Name

CDR_PUB_API_INITIALIZATION.Initialization

Signature

```
PROCEDURE INITIALIZATION(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
```

```
PI_VPKGNAME IN VARCHAR2  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_VPKGNAME This is used internally to pass the external API package name.

Verify Whether an API is Enabled

Use this API to find out whether or not the API you want to use is enabled.

Name

CDR_PUB_API_INITIALIZATION.IsAPIenabled

Signature

```
FUNCTION ISAPIENABLED(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL  
) RETURN BOOLEAN;
```

Return

BOOLEAN

- True: The API is enabled.
- False: It is disabled.

Parameters

This API has standard parameters. See [Standard Parameters](#) for details.

Enable an API

Use this API to enable LSH APIs that you want to use in a session. This API must be called at the beginning of each Program that uses LSH APIs.

Name

CDR_PUB_API_INITIALIZATION.EnableAPIs

Signature

```
PROCEDURE ENABLEAPIS(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  X_RETURN_STATUS OUT VARCHAR2,  
  X_MSG_COUNT OUT NUMBER,  
  X_MSG_DATA OUT VARCHAR2  
);
```

Parameters

This API has standard parameters. See [Standard Parameters](#) for details.

Disable an API

Use this API to disable LSH APIs that you have used in a session. Call this API at the end of each Program that uses LSH APIs.

Name

CDR_PUB_API_INITIALIZATION.DisableAPIs

Signature

```
Procedure disableAPIs (  
  p_api_version IN NUMBER  
  ,p_init_msg_list IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE  
  ,p_commit IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE  
  ,p_validation_level IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL  
  ,x_return_status OUT NOCOPY VARCHAR2  
  ,x_msg_count OUT NOCOPY NUMBER  
  ,x_msg_data OUT NOCOPY VARCHAR2  
);
```

Parameters

This API has standard parameters. See [Standard Parameters](#) for details.

Get Factory Support

This is a public interface that hosts utility APIs for other packages.

This section contains the following topics:

- [Get a Naming Version Object](#)
- [Get a User ID](#)
- [Get a User Name](#)

Get a Naming Version Object

Use this API to retrieve a valid CDR_NAMING_VERSION_OBJ_TYPE parameter by passing the primary keys COMPANY_ID, OBJ_ID, and OBJ_VER to it.

Name

CDR_PUB_DEF_FACTORY_SUPPORT.GetNamingObject

Signature

```
FUNCTION GETNAMINGOBJECT(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  PI_NCOMPANYID IN CDR_NAMINGS.COMPANY_ID%TYPE,  
  PI_NOBJID IN CDR_NAMINGS.OBJ_ID%TYPE,
```

```

    PI_NOBJVER IN      CDR_NAMING_VERSIONS.OBJ_VER%TYPE,
    PO_CDRNAMING OUT    CDR_NAMING_VERSION_OBJ_TYPE
) RETURN BOOLEAN;

```

Return

BOOLEAN

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NCOMPANYID** (Mandatory) Enter the COMPANY_ID of the object. Use [Get a Company ID](#).
- **PI_NOBJID** (Mandatory) Enter the OBJ_ID of the object.
- **PI_NOBJVER** (Mandatory) Enter the OBJ_VER of the object.
- **PO_CDRNAMING** (Mandatory) This is the output from the API.

Get a User ID

Use this API to retrieve the User ID of a given LSH user name.

Name

CDR_PUB_DEF_FACTORY_SUPPORT.getUserID

Signature

```

FUNCTION getUserID(
    P_API_VERSION IN      NUMBER,
    P_INIT_MSG_LIST IN    VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
    P_COMMIT IN          VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
    P_VALIDATION_LEVEL IN  NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
    P_USERNAME IN        VARCHAR2
    RETURN CDR_DF_NAMING_V.CHECKED_OUT_ID%type
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

P_USER_NAME (Mandatory) The LSH application user name.

Get a User Name

Use this API to retrieve the current user name.

Name

CDR_PUB_DEF_FACTORY_SUPPORT.GetUserName

Signature

```

FUNCTION GETUSERNAME(
    P_API_VERSION IN      NUMBER,
    P_INIT_MSG_LIST IN    VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
    P_COMMIT IN          VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
    P_VALIDATION_LEVEL IN  NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,

```

```
PI_USERID IN NUMBER
) RETURN VARCHAR2;
```

Return

Type VARCHAR2

Description VARCHAR2.

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_USERID (Mandatory) Enter the User ID. Use CDR_PUB_DEF_FACTORY_SUPPORT.GETUSERID to get the ID of the current user.

Get Factory Utilities

This is a public interface that hosts utility APIs for other packages.

This section contains the following topics:

- [Get a Base Object Type](#)
- [Get a Company ID](#)

Get a Base Object Type

Use this API to retrieve all details of an object from CDR_BASE_OBJ_TYPE table, by passing the object's primary key values: COMPANY_ID, OBJ_ID, and OBJ_VER.

Name

CDR_PUB_DEF_FACTORY_UTILS.GetCDRBaseObject

Signature

```
FUNCTION GETCDRBASEOBJECT (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PI_COMPANYID IN CDR_NAMINGS.COMPANY_ID%TYPE,
  PI_OBJID IN CDR_NAMINGS.OBJ_ID%TYPE,
  PI_OBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE
) RETURN CDR_BASE_OBJ_TYPE;
```

Return

Type CDR_BASE_OBJ_TYPE

Description CDR_BASE_OBJ_TYPE

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPANYID** (Mandatory) Enter the COMPANY_ID of the object
- **PI_OBJID** (Mandatory) Enter the OBJ_ID of the object
- **PI_OBJVER** (Mandatory) Enter the OBJ_VER of the object

Get a Company ID

Use this API to retrieve the COMPANY_ID of a given object. The object is identified from the context that this API is used in.

Name

CDR_PUB_DEF_FACTORY_UTILS.GetCompanyID

Signature

```
FUNCTION GETCOMPANYID(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL  
) RETURN NUMBER;
```

Return

Type NUMBER

Parameters

This API has standard parameters. See [Standard Parameters](#)) for details.

Get Factory Validations

This is a public interface that hosts APIs for checking object validation on various objects. These APIs are tools to automatically validate objects without having to manually set their attributes to validate them.

This section contains the following topics:

- [Validate a Namespace](#)
- [Validate a Reference](#)

Validate a Namespace

Use this API to validate whether a given object is created in a valid parent; for example, you may want to check if a Program Definition is a valid parent of a Table Descriptor.

Name

CDR_PUB_DEF_FACTORY_VALIDATE.ValidateNamespace

Signature

```
FUNCTION VALIDATENAMESPACE(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE  
) RETURN BOOLEAN;
```

Return

Type BOOLEAN

If the function returns True, then the reference is valid. Otherwise, it's invalid.

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_SOURCECDRNAMING (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes.

For OBJECT_TYPE_RC enter the appropriate value for the object for which you want to validate a reference.

Other required attributes are:

COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_TYPE_RC,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER,REF_COMPANY_ID,REF_OBJ_ID,REF_OBJ_VER

Validate a Reference

Use this API to validate the definition specified for the given object id.

Name

CDR_PUB_DEF_FACTORY_VALIDATE.ValidateReference

Signature

```
FUNCTION VALIDATEREFERENCE (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE
) RETURN BOOLEAN;
```

Return

Type BOOLEAN

If the function returns True, then the reference is valid. Otherwise, it's invalid.

- True: The referenced object is valid.
- False: The references object is not valid.

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_SOURCECDRNAMING (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes.

For OBJECT_TYPE_RC enter the appropriate value for the object for which you want to validate a reference.

Other required attributes are:

COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_TYPE_RC,NAMESPACE_OBJ_ID,NAMESPACE
_OBJ_VER,REF_COMPANY_ID,REF_OBJ_ID,REF_OBJ_VER

Get Data from Object Naming Tables

This is a public interface that is used to retrieve data from naming-related tables.

This section contains the following topics:

- [Get the Latest Version](#)
- [Get a Maximum Version](#)
- [Get the Type of a Naming Object](#)
- [Get an Object's Naming Version](#)
- [Get an Object's Subtype ID](#)
- [Get an Object's Checkout Status](#)
- [Get Checkout Properties](#)
- [Get a Naming Object's Parent](#)
- [Get a Parent Naming Object](#)
- [Get the Latest Version of the Parent Object](#)
- [Get the Naming Status of a Parent Object](#)
- [Get the Validation Status of a Parent Object](#)
- [Get a Definition Object](#)
- [Get a Lookup Meaning](#)
- [Find Whether an Object is an Instance](#)
- [Find Whether Checked Out By Current User](#)
- [Find Whether a Checkout is User-Specific](#)
- [Find Whether Checkout is Implicit](#)

Get the Latest Version

Use this API to retrieve the latest version available for a given object.

Name

CDR_PUB_DF_NAMING_UTIL.GetLastVersion

Signature

```
FUNCTION GETLASTVERSION(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  PI_BASEOBJECT IN CDR_BASE_OBJ_TYPE  
) RETURN NUMBER;
```

Return

Type NUMBER

Description number

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_BASEOBJECT (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE.

The required attributes are

COMPANY_ID,OBJECT_ID,OBJECT_VER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

Get a Maximum Version

Use this API to get the maximum versions of a specified object and its namespace.

Name

CDR_PUB_DF_NAMING_UTIL.GetMaxObjAndNsVersions

Signature

```
PROCEDURE GETMAXOBJANDNSVERSIONS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_COMPID IN NUMBER,
  PI_OBJID IN NUMBER,
  PO_MAXOBJVER OUT NUMBER,
  PO_MAXNSOBJVER OUT NUMBER
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPID** (Mandatory) Enter the COMPANY_ID of the given object.
- **PI_OBJID** (Mandatory) Enter the OBJ_ID of the given object.
- **PO_MAXOBJVER** This is an output parameter. It returns the maximum version of the given object.
- **PO_MAXNSOBJVER** This is an output parameter. It returns the maximum version of the Namespace of the given object.

Get the Type of a Naming Object

Use this API to get the type of a specified naming object.

Name

CDR_PUB_DF_NAMING_UTIL.GetNamingObjectType

Signature

```

FUNCTION GETNAMINGOBJECTTYPE (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PIO_BASEOBJECT IN CDR_BASE_OBJ_TYPE
) RETURN VARCHAR2;

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_BASEOBJECT (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. The required attributes are COMPANY_ID,OBJECT_ID,OBJECT_VER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

Get an Object's Naming Version

Use this API to retrieve an initialized object of table type CDR_NAMING_VERSION_OBJ_TYPE for a given naming object.

Name

CDR_PUB_DF_NAMING_UTIL. GetNamingVersionObject

Signature

```

FUNCTION GETNAMINGVERSIONOBJECT (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PI_BASEOBJECT IN CDR_BASE_OBJ_TYPE
) RETURN CDR_NAMING_VERSION_OBJ_TYPE;

```

Return

Type CDR_NAMING_VERSION_OBJ_TYPE

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_BASEOBJECT (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE.

The required attributes are COMPANY_ID,OBJECT_ID,OBJECT_VER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

Get an Object's Subtype ID

Use this API to retrieve the object subtype ID of a given naming object.

Name

CDR_PUB_DF_NAMING_UTIL.GetObjectSubtypeID

Signature

```
FUNCTION GETOBJECTSUBTYPEID(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PI_BASEOBJECT IN CDR_BASE_OBJ_TYPE
) RETURN NUMBER;
```

Return

Type NUMBER

Description Number

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_BASEOBJECT (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE.

The required attributes are

COMPANY_ID,OBJECT_ID,OBJECT_VER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

Get an Object's Checkout Status

Use this API to find out whether or not a naming object is checked out.

Name

CDR_PUB_DF_NAMING_UTIL.IsNamingCheckedOut

Signature

```
FUNCTION ISNAMINGCHECKEDOUT(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PIO_BASEOBJECT IN CDR_BASE_OBJ_TYPE
) RETURN BOOLEAN;
```

Return

Type BOOLEAN

Description Boolean

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_BASEOBJECT (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE.

The required attributes are

COMPANY_ID,OBJECT_ID,OBJECT_VER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

Get Checkout Properties

Use this API to retrieve the checkout status and implicit checkout property of a specified object.

Name

CDR_PUB_DF_NAMING_UTIL.GetChkoutProp

Signature

```
PROCEDURE GETCHKOUTPROP(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  X_RETURN_STATUS OUT VARCHAR2,  
  X_MSG_COUNT OUT NUMBER,  
  X_MSG_DATA OUT VARCHAR2,  
  PI_COMPID IN NUMBER,  
  PI_OBJID IN NUMBER,  
  PO_CHKOUTSTATUS OUT VARCHAR2,  
  PO_CHKIMPLPROP OUT VARCHAR2  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPID** (Mandatory) Enter the COMPANY_ID of the given object.
- **PI_OBJID** (Mandatory) Enter the OBJ_ID of the given object.
- **PO_CHKOUTSTATUS** This is an output parameter. It returns the checkout status of the given object
- **PO_CHKIMPLPROP** This is an output parameter. It returns the implicit checkout property of the given object.

Get a Naming Object's Parent

Use this API to retrieve the parent object of a given naming object.

Name

CDR_PUB_DF_NAMING_UTIL.GetParentNaming

Signature

```
FUNCTION GETPARENTNAMING(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  PI_BASEOBJECT IN CDR_BASE_OBJ_TYPE  
) RETURN CDR_BASE_OBJ_TYPE;
```

Return

Type CDR_BASE_OBJ_TYPE

Description CDR_BASE_OBJ_TYPE

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_BASEOBJECT (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE.

The required attributes are

COMPANY_ID,OBJECT_ID,OBJECT_VER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

Get a Parent Naming Object

Use this API to retrieve the parent object of a naming object.

Name

CDR_PUB_DF_NAMING_UTIL.GetParentNaming

Signature

```
FUNCTION GETPARENTNAMING(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PI_BASEOBJECT IN CDR_BASE_OBJ_TYPE
) RETURN CDR_BASE_OBJ_TYPE;
```

Return

Type CDR_BASE_OBJ_TYPE

Description CDR_BASE_OBJ_TYPE

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_BASEOBJECT (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE.

The required attributes are

COMPANY_ID,OBJECT_ID,OBJECT_VER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER

Get the Latest Version of the Parent Object

Use this API to retrieve the latest version of the parent of the given object.

Name

CDR_PUB_DF_NAMING_UTIL.GetLatestVersionOfParent

Signature

```
FUNCTION GETLATESTVERSIONOFPARENT(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PI_BASEOBJECT IN CDR_BASE_OBJ_TYPE
) RETURN CDR_BASE_OBJ_TYPE;
```

Return

Type CDR_BASE_OBJ_TYPE

Description cdr_base_obj_type

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_BASEOBJECT (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE.

The required attributes are

COMPANY_ID,OBJECT_ID,OBJECT_VER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

Get the Naming Status of a Parent Object

Use this API to get the naming status of the parent object of the specified object

Name

CDR_PUB_DF_NAMING_UTIL.GetParentNamingStatus

Signature

```
FUNCTION GETPARENTNAMINGSTATUS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PI_COMPANYID IN CDR_NAMINGS.COMPANY_ID%TYPE,
  PI_NSOBJID IN CDR_NAMINGS.OBJ_ID%TYPE,
  PI_NSOBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE
) RETURN VARCHAR2;
```

Return

Type VARCHAR2

Description varchar2

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPANYID** (Mandatory) Enter the COMPANY_ID of the object.
- **PI_NSOBJID** (Mandatory) Enter the OBJ_ID of the given object.
- **PI_NSOBJVER** (Mandatory) Enter the OBJ_VER of the given object.

Get the Validation Status of a Parent Object

Use this API to get the validation status of the parent object of the specified object

Name

CDR_PUB_DF_NAMING_UTIL.GetParentValidationStatus

Signature

```

FUNCTION GETPARENTVALIDATIONSTATUS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PI_COMPANYID IN CDR_NAMINGS.COMPANY_ID%TYPE,
  PI_NSOBJID IN CDR_NAMINGS.OBJ_ID%TYPE,
  PI_NSOBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE
) RETURN VARCHAR2;

```

Return

Type VARCHAR2

Description varchar2

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPANYID** (Mandatory) This refers to the company id of the given object.
- **PI_NSOBJID** (Mandatory) Enter the OBJ_ID of the given object.
- **PI_NSOBJVER** (Mandatory) Enter the OBJ_VER of the given object.

Get a Definition Object

Use this API to retrieve the definition object that the given instance object points to.

Name

CDR_PUB_DF_NAMING_UTIL.GetRefNaming

Signature

```

FUNCTION GETREFNAMING (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PI_BASEOBJECT IN CDR_BASE_OBJ_TYPE
) RETURN CDR_BASE_OBJ_TYPE;

```

Return

Type CDR_BASE_OBJ_TYPE

Description CDR_BASE_OBJ_TYPE

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_BASEOBJECT (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE.

The required attributes are

COMPANY_ID,OBJECT_ID,OBJECT_VER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

Get a Lookup Meaning

Use this API to get the Lookup Meaning for a Lookup Type and Code

Name

CDR_PUB_DF_NAMING_UTIL.GetLookupMeaning

Signature

```
PROCEDURE GETLOOKUPMEANING(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  X_RETURN_STATUS OUT VARCHAR2,  
  X_MSG_COUNT OUT NUMBER,  
  X_MSG_DATA OUT VARCHAR2,  
  PI_LOOKUPTYPE IN VARCHAR2,  
  PI_LOOKUPCODE IN VARCHAR2,  
  PO_LOOKUPMEANING OUT VARCHAR2  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_LOOKUPTYPE** (Mandatory) Enter the Lookup Type
- **PI_LOOKUPCODE** (Mandatory) Enter the Lookup Code
- **PO_LOOKUPMEANING** This is an output parameter. It returns the Lookup Meaning.

Find Whether an Object is an Instance

Use this API to check if the given naming object is an instance.

Name

CDR_PUB_DF_NAMING_UTIL.IsInstance

Signature

```
FUNCTION ISINSTANCE(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  PI_OBJECT_TYPE_RC IN VARCHAR2  
) RETURN VARCHAR2;
```

Return

Type VARCHAR2

Description varchar2

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_OBJECT_TYPE_RC (Mandatory) Object Type RC.

Find Whether Checked Out By Current User

Use this API to find out whether the given naming object is checked out by the current user.

Name

CDR_PUB_DF_NAMING_UTIL.IsCheckedOutByUser

Signature

```
FUNCTION ISCHECKEDOUTBYUSER(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PIO_BASEOBJECT IN CDR_BASE_OBJ_TYPE
) RETURN BOOLEAN;
```

Return

Type BOOLEAN Description boolean

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_BASEOBJECT (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE.

The required attributes are

COMPANY_ID,OBJECT_ID,OBJECT_VER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

Find Whether a Checkout is User-Specific

Use this API to find out if an object checkout is user specific or non-user specific. Only the user who checked out a user specific object can check it in; whereas any user may check in a non-user specific object.

Name

CDR_PUB_DF_NAMING_UTIL.IsCheckOutUserSpecific

Signature

```
FUNCTION ISCHECKOUTUSERSPECIFIC(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PI_SOURCECDRNAMING IN CDR_NAMING_VERSION_OBJ_TYPE
) RETURN BOOLEAN;
```

Return

Type BOOLEAN

Description Boolean True or False

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_SOURCECDRNAMING (Mandatory) This is a parameter of type `cdr_naming_versions_obj_type`.

The following attributes are required: `COMPANY_ID`, `OBJECT_TYPE_RC`, `NAME`, `NAMESPACE_OBJ_ID`, `NAMESPACE_OBJ_VER`, `OWNING_LOCATION_RC`, `OBJECT_SUBTYPE_ID`, `DESCRIPTION`, `REF_COMPANY_ID`, `REF_OBJ_ID`, `REF_OBJ_VER`.

Find Whether Checkout is Implicit

Use this API to find out whether a naming object is checked out implicitly.

Name

`CDR_PUB_DF_NAMING_UTIL.IsCheckOutImplicit`

Signature

```
FUNCTION ISCHECKOUTIMPLICIT(  
    P_API_VERSION IN NUMBER,  
    P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
    P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
    P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
    PI_OBJECT_TYPE_RC IN VARCHAR2,  
    PI_ISINSTONLY IN VARCHAR2  
) RETURN BOOLEAN;
```

Return

Type `BOOLEAN` Description `boolean`

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_OBJECT_TYPE_RC** (Mandatory) Enter the Object Type.
- **PI_ISINSTONLY** (Mandatory) This will have the value 'YES' or 'NO', to indicate whether it is called from an Instance or a Definition.

Define and Modify Adapters

This package is used to create adapter domains and adapter areas for user defined adapters.

This section contains the following topics:

- [Create an Adapter Domain](#)
- [Modify an Adapter Domain](#)
- [Create an Adapter Area](#)
- [Modify an Adapter Area](#)
- [Populate a Tech Type Table](#)
- [Modify a Tech Type Table](#)

Create an Adapter Domain

Use this API to create an Adapter Domain.

Name

CDR_PUB_ATK_ADAPTER.CreateAdapterDomain

Signature

```
PROCEDURE CREATEADAPTERDOMAIN(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_ADAPTERDOMAINNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_ADAPTERDOMAINNAMING (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values for the Adapter Domain that you are creating. For OBJECT_TYPE_RC enter \$OBJTYPES\$ADAPTERDOMAIN.

The following attributes are required: COMPANY_ID,NAME

Modify an Adapter Domain

Use this API to modify an Adapter Domain.

Name

CDR_PUB_ATK_ADAPTER.ModifyAdapterDomain

Signature

```
PROCEDURE MODIFYADAPTERDOMAIN(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT NOCOPY VARCHAR2,
  X_MSG_COUNT OUT NOCOPY NUMBER,
  X_MSG_DATA OUT NOCOPY VARCHAR2,
  PIO_ADAPTERDOMAINNAMING IN OUT NOCOPY CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PARAM P_API_VERSION** (Mandatory). Enter the current version of the API you are calling. The API compares the version numbers of incoming calls to its current version number and returns an error if they are incompatible.

- **PARAM P_INIT_MSG_LIST** (Optional). Accept the default value (FND_API.G_FALSE) to ensure that this individual API does not initialize the message list upon completion. Pass FND_API.G_TRUE to override the default behavior.
- **PARAM P_COMMIT** (Optional). Accept the default value (FND_API.G_FALSE) to ensure that this individual API does not get committed upon completion. Pass FND_API.G_TRUE to override the default behavior.
- **PARAM P_VALIDATION_LEVEL** (Optional). Accept the default value to perform full validation. No other values are currently supported.
- **PARAM X_RETURN_STATUS**. This output parameter returns the end status of the API: (S) Success, (E) Error or (U) Unexpected Error.
- **PARAM X_MSG_COUNT**. This output parameter returns the count of error messages if the return status is other than *Success*.
- **PARAM X_MSG_DATA**. This output parameter returns the text of the error message, if the message count is 1. If there are more than one message, use `cdr_pub_msg_pub.get` to retrieve the messages.
- **PARAM PIO_ADAPTERDOMAINNAMING** (Mandatory). This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Adapter Domain and enter new values for the attributes you want to modify. All attributes are required. For OBJECT_TYPE_RC enter \$OBJTYPES\$ADAPTERDOMAIN.

Create an Adapter Area

Use this API to create an Adapter Area.

Name

CDR_PUB_ATK_ADAPTER.CreateAdapterArea

Signature

```
PROCEDURE CREATEADAPTERAREA(
  P_API_VERSION    IN      NUMBER,
  P_INIT_MSG_LIST  IN      VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT         IN      VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN    NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS  OUT     VARCHAR2,
  X_MSG_COUNT      OUT     NUMBER,
  X_MSG_DATA       OUT     VARCHAR2,
  PIO_ADAPTERAREANAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PIO_ADAPTERAREAROW IN OUT   CDR_ADAPTER_AREAS%ROWTYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_ADAPTERAREANAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values for the adapter area that you are creating.
- **PIO_ADAPTERAREAROW** (Mandatory) This is a parameter of row type CDR_ADAPTER_AREAS table. Enter values specific for the adapter area that you are creating. For OBJECT_TYPE_RC enter \$OBJTYPES\$ADAPTERAREA. The following attributes are required: COMPANY_ID, NAME

Modify an Adapter Area

Use this API to modify an Adapter Area.

Name

CDR_PUB_ATK_ADAPTER.ModifyAdapterArea

Signature

```
PROCEDURE MODIFYADAPTERAREA(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT NOCOPY VARCHAR2,
  X_MSG_COUNT OUT NOCOPY NUMBER,
  X_MSG_DATA OUT NOCOPY VARCHAR2,
  PIO_ADAPTERAREANAMING IN OUT NOCOPY CDR_NAMING_VERSION_OBJ_TYPE,
  PIO_ADAPTERAREAROW IN OUT NOCOPY CDR_ADAPTER_AREAS%ROWTYPE,
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- PARAM P_INIT_MSG_LIST (Optional). Accept the default value (FND_API.G_FALSE) to ensure that this individual API does not initialize the message list upon completion. Pass FND_API.G_TRUE to override the default behavior.
- PARAM P_COMMIT (Optional). Accept the default value (FND_API.G_FALSE) to ensure that this individual API does not get committed upon completion. Pass FND_API.G_TRUE to override the default behavior.
- PARAM P_VALIDATION_LEVEL (Optional). Accept the default value to perform full validation. No other values are currently supported.
- PARAM X_RETURN_STATUS. This output parameter returns the end status of the API: (S) Success, (E) Error or (U) Unexpected Error.
- PARAM X_MSG_COUNT. This output parameter returns the count of error messages if the return status is other than *Success*.
- PARAM X_MSG_DATA. This output parameter returns the text of the error message, if the message count is 1. If there are more than one message, use `cdr_pub_msg_pub.get` to retrieve the messages.
- PARAM PIO_ADAPTERDOMAINNAMING (Mandatory). This is a parameter of table-type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Adapter Area and enter new values for the attributes you want to modify. All attributes are required.
- PARAM PIO_ADAPTERAREAROW (Mandatory). This is a parameter of row-type CDR_ADAPTER_AREAS table.
- PARAM P_API_VERSION (Mandatory). Enter the current version of the API you are calling. The API compares the version numbers of incoming calls to its current version number and returns an error if they are incompatible.
For OBJECT_TYPE_RC enter \$OBJTYPES\$ADAPTERAREA.

Populate a Tech Type Table

Use this API to populate a Tech Type Table.

Name

CDR_PUB_ATK_ADAPTER.PopulateTechTypes

Signature

```
PROCEDURE POPULATETECHTYPES(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  X_RETURN_STATUS OUT VARCHAR2,  
  X_MSG_COUNT OUT NUMBER,  
  X_MSG_DATA OUT VARCHAR2,  
  PIO_TECHTYPE_ROW IN OUT CDR_TECH_TYPES%ROWTYPE  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_TECHTYPE_ROW (Mandatory) This is a parameter of row type `cdr_tech_types` table. Enter values specific for the tech type that you are creating.

Modify a Tech Type Table

Use this API to modify a Tech Type Table.

Name

CDR_PUB_ATK_ADAPTER.ModifyTechTypes

Signature

```
PROCEDURE MODIFYTECHTYPE(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  X_RETURN_STATUS OUT NOCOPY VARCHAR2,  
  X_MSG_COUNT OUT NOCOPY NUMBER,  
  X_MSG_DATA OUT NOCOPY VARCHAR2,  
  PIO_TECHTYPE_ROW IN OUT NOCOPY CDR_TECH_TYPES%ROWTYPE,  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PARAM P_API_VERSION** (Mandatory). Enter the current version of the API you are calling. The API compares the version numbers of incoming calls to its current version number and returns an error if they are incompatible.

- `PARAM P_INIT_MSG_LIST` (Optional). Accept the default value (`FND_API.G_FALSE`) to ensure that this individual API does not initialize the message list upon completion. Pass `FND_API.G_TRUE` to override the default behavior.
- `PARAM P_COMMIT` (Optional). Accept the default value (`FND_API.G_FALSE`) to ensure that this individual API does not get committed upon completion. Pass `FND_API.G_TRUE` to override the default behavior.
- `PARAM P_VALIDATION_LEVEL` (Optional). Accept the default value to perform full validation. No other values are currently supported.
- `PARAM X_RETURN_STATUS`. This output parameter returns the end status of the API: (S) Success, (E) Error or (U) Unexpected Error.
- `PARAM X_MSG_COUNT`. This output parameter returns the count of error messages if the return status is other than *Success*.
- `PARAM X_MSG_DATA`. This output parameter returns the text of the error message, if the message count is 1. If there are more than one message, use `cdr_pub_msg_pub.get` to retrieve the messages.
- `PARAM PIO_TECHTYPEPEROW` (Mandatory). This is a parameter of row type `cdr_tech_types` table. Enter values specific for the tech type that you want to update.

Host Definition Constants

This is a public interface that hosts definition constants for Oracle LSH APIs.

Name

`CDR_PUB_DEF_CONSTANTS`

Read Messages

This is a public interface for reporting using messages from the system's message stack. See [Code Example Using Security and Error Message APIs](#) for an example of a program that calls this reporting API.

This section contains the following topics:

- [Get a Message](#)
- [Get a Message Count](#)
- [Initialize a Message Stack](#)

Get a Message

Use this API to retrieve messages from the message stack.

Name

`CDR_PUB_MSG_PUB.Get`

Signature

```
FUNCTION GET(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
```

```
P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
P_MSG_INDEX IN NUMBER := G_NEXT,  
P_ENCODED IN VARCHAR2 := 'T'  
) RETURN VARCHAR2;
```

Return

Type VARCHAR2

Description varchar2 Message Text

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **P_MSG_INDEX** (Mandatory) Enter the number of the message you want to retrieve; for example, if you enter the number 1, the first message is retrieved from the message stack.
- **P_ENCODED** (Mandatory) Enter "T" if you want the message to be encoded, and "F" if you do not.

Get a Message Count

Use this API to retrieve the count of messages in the message stack. This API returns the G_MSG_COUNT value.

Name

CDR_PUB_MSG_PUB.Count_Msg

Signature

```
FUNCTION COUNT_MSG(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL  
) RETURN NUMBER;
```

Return

Type NUMBER

Description Number of messages in the stack

Parameters

This API has standard parameters (see [Standard Parameters](#)).

Initialize a Message Stack

Use this API to initialize the global message table. This API clears the G_MSG_TBL and resets all its global variables, except the message level threshold value.

Name

CDR_PUB_MSG_PUB.Initialize

Signature

```
PROCEDURE INITIALIZE(
  P_API_VERSION IN    NUMBER,
  P_INIT_MSG_LIST IN   VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN        VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN  NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT   VARCHAR2,
  X_MSG_COUNT OUT      NUMBER,
  X_MSG_DATA OUT       VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)).

Change Tablespaces

Use this API to alter the tablespace of Table instances and indexes in a single container—Domain, Application Area, or Work Area—identified recursively. This may be helpful if you want to archive data or if the current tablespace runs out of room. You can associate Table instances and indexes with the same tablespace or two different ones.

The API generates a script to change the tablespace attribute of all table instances and indexes in the container you specify. It also analyzes the effect of the change and generates a log file that may include errors or warnings.

To Use this API:

1. Take a backup of the database.
2. Run the API with a database account associated with an application user.
3. Check the generated log file for errors and warnings before running the generated script.
4. Run the script with a database account with DBA privileges.

Note:

If a Work Area is installed after its Table instances and indexes have been changed to a different tablespace, some of the new tablespace associations are lost:

- Table instances remain in the new tablespace.
- Temporary tables revert to the default tablespace.
- Nonunique and bitmap indexes are associated with the new tablespace of the Table instances, even if they had been in a different new tablespace.
- All other indexes revert to the default tablespace.

You can run the script again to properly reassociate all objects with the preferred tablespaces.

Name

CDR_PUB_REORG_TABLES.genTablesTablespaceAlterScript

Signature

```

procedure genTablesTablespaceAlterScript(
    p_api_version      IN NUMBER ,
    p_init_msg_list    IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
    p_validation_level IN NUMBER DEFAULT
        CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
    pi_companyId       IN cdr_namings.company_id%TYPE,
    pi_objId           IN cdr_namings.obj_id%TYPE,
    pi_targetTabTablespace IN VARCHAR2,
    pi_targetIdxTablespace IN VARCHAR2,
    po_cReturnClob OUT NOCOPY clob,
    po_cReturnLogClob OUT NOCOPY clob,
    x_return_status OUT NOCOPY VARCHAR2,
    x_msg_count OUT NOCOPY NUMBER,
    x_msg_data OUT NOCOPY VARCHAR2);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:



Note:

Unlike other LSH public APIs, this API has the standard P_COMMIT parameter permanently set to FALSE.

- **PI_COMPANYID** (Mandatory). Enter the company ID of the container object—Domain, Application Area, or Work Area—that contains the table instances whose tablespace you want to change. To get your company ID, use CDR_PUB_DEF_FACTORY_UTILS.GetCompanyId.
- **PI_OBJID** (Mandatory). Enter the object ID of the container object—Domain, Application Area, or Work Area—that contains the table instances whose tablespace you want to change.
- **PI_TARGETTABTABLESPACE** (Mandatory). Enter the name of the new tablespace for tables.
- **PI_TARGETIDXTABLESPACE** (Mandatory). Enter the name of the new tablespace for indexes.
- **PO_CRETURNCLOB** The API returns a generated script CLOB output.
- **PO_CRETURNLOGCLOB** The API returns a generated log CLOB output.

Execution Setups

This is a public interface for Execution Setup-related operations, including creating, modifying, and removing Execution Setups. It also includes functions for checking Execution Setups in and out.

This chapter contains this section:

- [Create and Modify Execution Setups](#)

Create and Modify Execution Setups

This section contains the following topics:

- [Create an Execution Setup](#)
- [Check Out an Execution Setup](#)
- [Modify an Execution Setup](#)
- [Modify a Parameter](#)
- [Modify an Execution Setup Parameter](#)
- [Load Parameter Details](#)
- [Copy an Execution Setup](#)
- [Check In an Execution Setup](#)
- [Submit an Execution Setup](#)
- [Submit an Execution Setup for Instances](#)
- [Submit an Execution Setup for Compound Objects](#)
- [Upgrade an Execution Setup](#)
- [Upgrade All Execution Setups](#)
- [Make an Execution Setup Active](#)
- [Remove an Execution Setup](#)

Create an Execution Setup

Use this API to create a new Execution Setup.

Name

CDR_PUB_DF_EXECUTIONSETUP.CreateExecutionSetup

Signature

```
PROCEDURE CREATEEXECUTIONSETUP (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
```

```
X_RETURN_STATUS OUT VARCHAR2,
X_MSG_COUNT OUT NUMBER,
X_MSG_DATA OUT VARCHAR2,
PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
PO_DEFCLASSIFICATIONCOLL IN CDR_CLASSIFICATIONS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. For OBJECT_TYPE_RC enter \$OBJTYPES\$EXECSETUP.
- **PO_DEFCLASSIFICATIONCOLL** (Optional) By default the new definition is classified according to the subtype you assigned it in the CDR_NAMING_VERSION_OBJ_TYPE. If you want to override the default classifications for one or more classification levels, use this parameter. This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID.

If you want the definition to inherit its classifications for a particular level from its parent, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are not relevant to Execution Setups. Do not enter any values for them. If you are not creating a new definition, do not enter values here.

Check Out an Execution Setup

Use this API to check out an Execution Setup.

Name

CDR_PUB_DF_EXECUTIONSETUP.CheckOutExecutionSetup

Signature

```
PROCEDURE CHECKOUTEXECUTIONSETUP (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_BASEOBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PI_COMMENT IN VARCHAR2,
  PI_ISINSTONLY IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Execution Setup that you want to check out.

The following attributes are required:

COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,
NAMESPACE_OBJ_VER.

- **PI_COMMENT** (Optional) Enter the reason you are checking out the Execution Setup.
- **PI_ISINSTONLY** (Mandatory) Enter \$YESNO\$NO.

Modify an Execution Setup

Use this API to modify an Execution Setup. You can change an Execution Setup's name and description. You must check out the Execution Setup before modifying it.

Name

CDR_PUB_DF_EXECUTIONSETUP.ModifyExecutionSetup

Signature

```
PROCEDURE MODIFYEXECUTIONSETUP (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

- **PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Execution Setup and enter new values for the attributes you want to modify. All attributes are required.

Note:

Use separate APIs for modifying the validation status and the version label:
CDR_PUB_VL_VALIDATION.UPDATEVALSTATUS and
CDR_PUB_DF_NAMING.UPDATEVERSIONLABEL.

Modify a Parameter

Use this API to modify Execution Setup parameters.

Name

CDR_PUB_DF_EXECUTIONSETUP.ModifyParameter

Signature

```
PROCEDURE MODIFYPARAMETER (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
```

```
P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT VARCHAR2,
X_MSG_COUNT OUT NUMBER,
X_MSG_DATA OUT VARCHAR2,
PI_CHANGEDPARAMETERCOLL IN CDR_SUBMISSION_DETAILS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_CHANGEDPARAMETERCOLL (Mandatory) This is a collection of CDR_SUBMISSION_DETAILS.Collection of Parameter Instances on which the modify operation has been requested.

Modify an Execution Setup Parameter

Use this API to modify the parameters of an Execution Setup.

Name

CDR_PUB_DF_EXECUTIONSETUP.ModifyYesParameters

Signature

```
PROCEDURE MODIFYYESPARAMETERS(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_PARAMETERCOLL IN OUT CDR_PARAMETER_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_PARAMETERCOLL (Mandatory) This is a collection of cdr_parameter_coll. Enter the values for parameters you want to change.

The attributes you can change are: read_only_flag_rc, mandatory_flag_rc, and visible_flag_rc. Enter \$yesno\$yes for yes, and \$yesno\$no for no.

Load Parameter Details

Use this API to insert all parameters into a CDR_ES_TEMP table before submitting Report Set instance and Work Flow instance jobs.

Name

CDR_PUB_DF_EXECUTIONSETUP.LoadESTempTable

Signature

```
PROCEDURE LOADESTEMPTABLE(
  P_API_VERSION IN NUMBER,
```

```
P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT VARCHAR2,
X_MSG_COUNT OUT NUMBER,
X_MSG_DATA OUT VARCHAR2,
PI_BASEOBJ IN CDR_BASE_OBJ_TYPE,
PI_NODEPRREFID IN NUMBER := NULL,
PI_NODEPRREFVER IN NUMBER := NULL,
PI_JOBID IN NUMBER := NULL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_BASEOBJ** (Mandatory) This is a parameter of cdr_base_obj type for the Execution Setup. Enter the necessary attributes.
- **PI_NODEPRREFID** (Mandatory) If you are submitting a single RSE, enter the prref_id of that RSE, else enter NULL.
- **PI_NODEPRREFVER** (Mandatory) If you are submitting a single RSE, enter the prref_ver of that RSE, else enter NULL.
- **PI_JOBID** (Mandatory) If you are re-submitting an existing job, enter the previous job_id, else enter NULL.

Copy an Execution Setup

Use this API to duplicate one or more Execution Setups for an object.

Name

CDR_PUB_DF_EXECUTIONSETUP.CopyExecutionSetup

Signature

```
PROCEDURE COPYEXECUTIONSETUP(
P_API_VERSION IN NUMBER,
P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT VARCHAR2,
X_MSG_COUNT OUT NUMBER,
X_MSG_DATA OUT VARCHAR2,
PI_EXECUTIONSETUP IN OUT CDR_BASE_OBJ_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

- **PI_EXECUTIONSETUP** (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES. For each Execution Setup that you want to copy, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.
The following attributes are required:
COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,
NAMESPACE_OBJ_VER.

Check In an Execution Setup

Use this API to check in an Execution Setup.

Name

CDR_PUB_DF_EXECUTIONSETUP.CheckInExecutionSetup

Signature

```
PROCEDURE CHECKINEXECUTIONSETUP(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_BASEOBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PI_COMMENT IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_BASEOBJECT** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Execution Setup that you want to check in.
The following attributes are required:
COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER
- **PI_COMMENT** (Optional) Enter the reason you are checking in the Execution Setup.

Submit an Execution Setup

Use this API to submit an Execution Setup.

Name

CDR_PUB_DF_EXECUTIONSETUP.SubmitExecutionSetup

Signature

```
PROCEDURE SUBMITEXECUTIONSETUP(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_EXECUTIONSETUP IN CDR_BASE_OBJ_TYPE,
  PI_CHANGEDSYSTEMPARAMETERCOLL IN CDR_SUBMISSION_DETAILS_COLL,
  PI_TICOLL IN CDR_SNAPSHOT_TABLE_COLL,
  PI_INCLUDEDOBJCOLL IN CDR_SUBMISSION_DETAILS_COLL,
  PI_CURRENTJOBID OUT VARCHAR2,
  PI_OUTPUTTITLE IN VARCHAR2,
```

```
PI_OUTPUTDESC IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_EXECUTIONSETUP** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Execution Setup that you want to submit.
The following attributes are required:
COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.
- **PIO_CHANGEDSYSTEMPARAMETERCOLL** (Mandatory) This is a parameter of cdr_submission_details_coll type.
You must provide values for the following system parameters: company_id (use CDR_DF_PUB_DEF_CONSTANTS.CURRENT_COMPANY_ID); submission_id (enter null); prref_id (enter -1), prref_ver (enter -1), parameter_ref_obj_id, and parameter_ref_obj_id. Query cdr_parameters on company_id, obj_id, and obj_ver to find values for the default_value attribute. Use this value to set the attribute parameter_value.
- **PI_TICOLL** (Mandatory) This is a collection of CDR_SNAPSHOT_TABLE_OBJ_TYPE.
- **PI_INCLUDEDOBJCOLL** (Mandatory) This is a collection of CDR_SUBMISSION_DETAILS_OBJ_TYPE that contains PRREF_IDs of Programs to include in the Execution Setup. For Report Sets and Report Set Entries, the user can include only selected Report Sets for execution. Enter only those PRREF_IDs.
- **PI_CURRENTJOBID** (Mandatory) Enter the JOB_ID of the Job that this Execution Setup submission created. This parameter is used to generate user's feedback.
- **PI_OUTPUTTITLE** (Mandatory) Enter a title for the output from this Execution Setup.
- **PI_OUTPUTDESC** (Mandatory) Enter the description for the output from this Execution Setup.

Submit an Execution Setup for Instances

Use this API to submit an Execution Setup for Report Set instances and Workflow instances. You must call the loadESTempTable API before calling this API.

Name

CDR_PUB_DF_EXECUTIONSETUP.SubmitExecutionSetup

Signature

```
PROCEDURE SUBMITEXECUTIONSETUP(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_EXECUTIONSETUP IN OUT CDR_BASE_OBJ_TYPE,
  PIO_CHANGEDSYSTEMPARAMETERCOLL IN OUT CDR_SUBMISSION_DETAILS_COLL,
  PI_TICOLL IN CDR_SNAPSHOT_TABLE_COLL,
  PO_CURRENTJOBID OUT VARCHAR2,
  PI_OUTPUTTITLE IN VARCHAR2,
```

```
PI_OUTPUTDESC IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_EXECUTIONSETUP** (Mandatory) This is a parameter of `cdr_base_obj_type`. Enter values for attributes that describe the Execution Setup: `COMPANY_ID`, `OBJ_ID`, `OBJ_VER`, `NAMESPACE_OBJ_ID`, `NAMESPACE_OBJ_VER`, `OBJECT_VERSION_NUMBER`.
- **PIO_CHANGEDSYSTEMPARAMETERCOLL** (Mandatory) This is a parameter of `cdr_submission_details_coll` type. You must provide values for the following system parameters: `company_id` (use `CDR_DF_PUB_DEF_CONSTANTS.CURRENT_COMPANY_ID`); `submission_id` (enter null); `prref_id` (enter -1), `prref_ver` (enter -1), `parameter_ref_obj_id`, and `parameter_ref_obj_id`. Query `cdr_parameters` on `company_id`, `obj_id`, and `obj_ver` to find values for the `default_value` attribute. Use this value to set the attribute `parameter_value`.
- **PI_TICOLL** (Mandatory) This is a collection of data snapshots. This value may be null if you want to use current data. Otherwise the required attributes are: `TI_OBJ_ID`, `TI_OBJ_VER`, `SRC_MASTER_JOB_ID`, `SRC_COMPANY_ID`
- **PO_CURRENTJOBID** (Mandatory) This is an output parameter. The system generates a Job ID for the submitted Execution Setup. You can print this parameter through your program.
- **PI_OUTUTTITLE** (Mandatory) Enter a title for the Execution Setup. It is easy to track an Execution Setup with a meaningful title.
- **PI_OUTPUTDESC** (Mandatory) Enter a description for the Execution Setup output.

Submit an Execution Setup for Compound Objects

Use this API to submit an Execution Setup for compound objects such as Report Sets and Workflows.

The API takes care of both, populating the temporary tables for execution and submitting the job, so that you do not need to invoke the `loadESTempTable` explicitly.

Name

`CDR_PUB_DF_EXECUTIONSETUP.SubmitExecutionSetup`

Signature

```
PROCEDURE SUBMITEXECUTIONSETUP(
P_API_VERSION IN NUMBER,
P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE
P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER,
X_MSG_DATA OUT NOCOPY VARCHAR2,
PI_EXECUTIONSETUP IN OUT NOCOPY CDR_BASE_OBJ_TYPE,
PIO_CHANGEDSYSTEMPARAMETERCOLL IN OUT NOCOPY CDR_SUBMISSION_DETAILS_COLL,
PI_TICOLL IN CDR_SNAPSHOT_TABLE_COLL,
PI_EXEPARAMCOLL IN OUT NOCOPY CDR_PARAMETER_COLL,
PI_EXEOBJCOLL IN OUT NOCOPY CDR_PARAMETER_COLL,
```

```
PI_NODEPRREFID IN NUMBER DEFAULT NULL,
PI_NODEPRREFVER IN NUMBER DEFAULT NULL,
PI_JOBID IN NUMBER DEFAULT NULL,
PO_JOBID OUT NOCOPY VARCHAR2,
PI_OUTPUTTITLE IN VARCHAR2,
PI_OUTPUTDESC IN VARCHAR2);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PARAM P_API_VERSION.** The API uses this parameter to compare the version numbers of incoming calls to its current version number, and returns an unexpected error if the versions are incompatible.
- **PARAM P_INIT_MSG_LIST.** Use this parameter to request that the API initialize the message list. By default, this parameter is set to FND_API.G_FALSE, meaning that APIs do not initialize the message list unless specifically instructed by the user.
- **PARAM P_COMMIT.** Use this parameter to instruct the API to commit after performing its function. By default, this parameter is set to FND_API.G_FALSE, meaning that APIs do not commit unless instructed by the user.
- **PARAM P_VALIDATION_LEVEL.** This parameter helps the API to determine those validation steps to execute and those to skip. The current behavior is that the API performs a full validation.
- **PARAM PI_EXECUTIONSETUP.** The base object type of Execution setup for which a Submit is requested.
- **PARAM PIO_CHANGEDSYSTEMPARAMETERCOLL.** The collection of SYSTEM parameters.
- **PARAM PI_TICOLL.** The collection of Table Instances referenced from the Object Instance hierarchy with the Currency information as specified by the user.
- **PARAM PI_EXEPARAMCOLL.** The collection of CDR_PARAMETER_OBJ_TYPE parameters. This can be passed as null, but if you want to overwrite a parameter's value for submission, then populate this with the Parameter object details and assign the DEFAULT_VALUE attribute to the overwritten parameter value. The other required attributes are COMPANY_ID, OBJ_ID, OBJ_VER and DEFAULT_VALUE.
- **PARAM PI_EXEOBJCOLL.** This is a collection of CDR_PARAMETER_OBJ_TYPE parameters that contains the PRREF_IDs of Programs to be included in the Execution Setup.
For Report Sets and Report Set Entries, enter the PRREF_IDs of those selected Report Sets that may be included for execution. Use PRREF_ID, PRREF_VER of Objects to OBJ_ID, OBJ_VER of CDR_PARAMETER_OBJ_TYPE. Set DEFAULT_VALUE as 'Y'. You do not need to assign other attributes except COMPANY_ID, OBJ_ID, OBJ_VER and DEFAULT_VALUE.
- **PARAM PI_NODEPRREFID.** To submit only a single node(RSE), pass its PrrefId; else, pass this parameter as null.
- **PARAM PI_NODEPRREFVER.** To submit only a single node, pass its PrrefVer; else, pass as null.
- **PARAM PI_JOBID.** To resubmit a job, pass the previous JobId; else, pass as null.
- **PARAM PO_JOBID.** The Job ID that is created during the submission.
- **PARAM PI_OUTPUTTITLE.** The suffix of the output's title.

- **PARAM PI_OUTPUTDESC.** The suffix of the output's description.

Upgrade an Execution Setup

Use this API to upgrade one single Execution Setup.

Name

CDR_PUB_DF_EXECUTIONSETUP.UpgradeExecSetup

Signature

```
PROCEDURE UPGRADEEXECSETUP (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_ESCOMPID IN NUMBER,
  PI_ESOBJID IN NUMBER,
  PI_ESOBJVER IN NUMBER,
  PO_UPGRADESTATUS IN OUT VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_ESCOMPID** (Mandatory) Enter the COMPANY_ID of the Execution Setup.
- **PI_ESOBJID** (Mandatory) Enter the OBJ_ID of the Execution Setup.
- **PI_ESOBJVER** (Mandatory) Enter the OBJ_VER of the Execution Setup.
- **PO_UPGRADESTATUS** This is an output parameter that indicates whether or not the Execution Setup's upgrade was successful.

Upgrade All Execution Setups

Use this API to upgrade all the Execution Setups associated with an object.

Name

CDR_PUB_DF_EXECUTIONSETUP.UpgradeExecSetups

Signature

```
PROCEDURE UPGRADEEXECSETUPS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_EOICOMPID IN NUMBER,
  PI_EOIOBJID IN NUMBER,
  PI_EOIOBJVER IN NUMBER,

```

```
PO_NOTRUNNABLEESLIST OUT CDR_BASE_OBJ_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_EOICOMPID** (Mandatory) Enter the COMPANY_ID of the executable object instance for which the Execution Setup is intended.
- **PI_EOIOBJID** (Mandatory) Enter the OBJ_ID of the executable object instance for which the Execution Setup is intended.
- **PI_EOIOBJVER** (Mandatory) Enter the OBJ_VER of the executable object instance for which the Execution Setup is intended.
- **PO_NOTRUNNABLEESLIST** This is an output parameter that returns a collection of CDR_BASE_OBJ_TYPE containing Execution Setups whose status has changed from Runnable to Not-Runnable.

Make an Execution Setup Active

Use this API to set the status of an Execution Setup to Active.

Name

CDR_PUB_DF_EXECUTIONSETUP.SetActive

Signature

```
PROCEDURE SETACTIVE(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_ESCOMPID IN NUMBER,
  PI_ESOBJID IN NUMBER,
  PI_ESOBJVER IN NUMBER
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_ESCOMPID** (Mandatory) Enter the COMPANY_ID of the Execution Setup.
- **PI_ESOBJID** (Mandatory) Enter the OBJ_ID of the Execution Setup.
- **PI_ESOBJVER** (Mandatory) Enter the OBJ_VER of the Execution Setup.

Remove an Execution Setup

Use this API to delete an Execution Setup.

Name

CDR_PUB_DF_EXECUTIONSETUP.RemoveExecutionSetup

Signature

```
PROCEDURE REMOVEEXECUTIONSETUP (
  P_API_VERSION IN      NUMBER,
  P_INIT_MSG_LIST IN    VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN          VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT   VARCHAR2,
  X_MSG_COUNT OUT       NUMBER,
  X_MSG_DATA OUT        VARCHAR2,
  PI_EXECUTIONSETUP IN OUT CDR_BASE_OBJ_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_EXECUTIONSETUP (Mandatory) This is a collection of CDR_BASE_OBJ_TYPES. For each Execution Setup that you want to remove, initialize a CDR_BASE_OBJ_TYPE and then extend the collection.

The following attributes are required:

COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.

21

Mappings

This is a public interface for mapping-related operations; including—creating and modifying mappings at the Table Descriptor and Column levels, creating a Table Descriptor from a Table instance, or a Table instance from a Table Descriptor, and mapping the two. It also includes functions for getting the unique PRREF_ID and PRREF_VER for the executables and Business Areas that contain Table Descriptors. You need these identifiers to run most of the mapping APIs.

This chapter contains the following section:

- [Create and Modify Mappings](#)

Create and Modify Mappings

This section contains the following topics:

- [Map a Column](#)
- [Map a Table Descriptor to a Table Instance](#)
- [Get a Table Instance ID](#)
- [Create a Table Descriptor from a Table Instance](#)
- [Create a Table Instance from a Table Descriptor](#)
- [Modify a Mapping Column](#)
- [Modify a Mapping at the Table Descriptor Level](#)
- [Get a PRREF_ID for an Executable in a Workflow](#)
- [Get a PRREF_ID for an Object in a Work Area](#)
- [Get a PRREF_ID for a Program in a Report Set](#)

Map a Column

Use this API to map a Table Descriptor's Columns to a Table instance's Columns using default criteria such as Name, Data Type, and Length. Before you run this API you must map the Table Descriptor and instance and note the Mapping ID and version.

Name

CDR_PUB_DF_MAPPING.GenerateDefaultMapping

Signature

```
PROCEDURE GENERATEDEFAULTMAPPING (  
  P_API_VERSION IN      NUMBER,  
  P_INIT_MSG_LIST IN    VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN        VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN  NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  X_RETURN_STATUS OUT   VARCHAR2,  
  X_MSG_COUNT OUT      NUMBER,
```

```

X_MSG_DATA OUT VARCHAR2,
PI_MAPPING_NAMING IN CDR_NAMING_VERSION_OBJ_TYPE
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_MAPPING_NAMING (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Mapping that you want to extend to the Column level.

The following attributes are required: OBJ_ID and OBJ_VER.

Map a Table Descriptor to a Table Instance

Use this API to map a Table Descriptor to a Table instance. You specify the Table Descriptor and Table instance and the API maps the columns if it is possible.

Name

CDR_PUB_DF_MAPPING.AutoMapTableDesc

Signature

```

PROCEDURE AUTOMAPTABLEDESC (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_PRRREFID IN CDR_PROGRAM_REFS.PRRREF_ID%TYPE,
  PI_PRRREFVER IN CDR_PROGRAM_REFS.PRRREF_VER%TYPE,
  PI_TDOBJ IN CDR_NAMING_VERSION_OBJ_TYPE,
  PI_TIOBJ IN CDR_NAMING_VERSION_OBJ_TYPE
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_PRRREFID** (Mandatory) Enter the PRRREF_ID of the executable object—Program, Load Set, Data Mart, Business Area that owns the Table Descriptor that you want to map. (Use other APIs in this package to get the PRRREF_ID.)
- **PI_PRRREFVER** (Mandatory) Enter the PRRREF_VER of the executable object or Business Area that owns the Table Descriptors that you want to map. (Use other APIs in this package to get the PRRREF_VER.)
- **PI_TDOBJ** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. Enter values to identify the Table Descriptor you want to map. The required attributes are: COMPANY_ID, OBJ_ID, OBJ_VER.
- **PI_TIOBJ** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. Enter values to identify the Table instance to which you want to map the Table Descriptor. The required attributes are: COMPANY_ID, OBJ_ID, OBJ_VER.

Get a Table Instance ID

Use this API to get the Object ID of the table instance that is mapped to a particular table descriptor. You can invoke this function within a PLSQL program.

While transforming source data into target data in Oracle DMW, it is needed at times, to flag target data. The Oracle DMW API used to assign flags to target data requires the Obj ID of the Table Instance as input. This API performs the task of getting the required Obj ID of the target Table Instance, in order that the Flag-related Oracle DMW APIs can be invoked.

Name

CDR_PUB_DF_MAPPING.Get_Tab_Inst_ID

Signature

```
FUNCTION GETTABINSTID(  
  PI_TABDESCNAME IN VARCHAR2,  
) RETURN NUMBER;
```

Return

Type NUMBER

Parameters

This API has the following parameter:

PI_TABDESCNAME (Mandatory). Enter the Oracle Name of the Table Descriptor whose mapped Table Instance ID you want to retrieve.

Create a Table Descriptor from a Table Instance

Use this API to create a Table Descriptor from an existing Table instance and map the two.

Name

CDR_PUB_DF_MAPPING.CreateTabDescFromTabInst

Signature

```
PROCEDURE CREATETABDESCFROMTABINST(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  X_RETURN_STATUS OUT VARCHAR2,  
  X_MSG_COUNT OUT NUMBER,  
  X_MSG_DATA OUT VARCHAR2,  
  PI_PRREFID IN CDR_PROGRAM_REFS.PRREF_ID%TYPE,  
  PI_PRREFVER IN CDR_PROGRAM_REFS.PRREF_VER%TYPE,  
  PI_TIOBJ IN CDR_NAMING_VERSION_OBJ_TYPE  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_PRREFID** (Mandatory) Enter the PRREF_ID of the executable object—Program, Load Set, Data Mart or Business Area, in which you want to create a Table Descriptor. (Use other APIs in this package to get this value.)
- **PI_PRREFVER** (Mandatory) Enter the PRREF_VER of the executable object or Business Area in which you want to create a Table Descriptor. (Use other APIs in this package to get this value.)
- **PI_TIOBJ** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. Enter values for the Table instance from which you want to create a Table Descriptor. The required attributes are: COMPANY_ID, OBJ_ID, OBJ_VER.

Create a Table Instance from a Table Descriptor

Use this API to create a Table instance from a Table Descriptor and map the two.

Name

CDR_PUB_DF_MAPPING.CreateTabInstFromTabDesc

Signature

```
PROCEDURE CREATETABINSTFROMTABDESC (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_PRREFID IN CDR_PROGRAM_REFS.PRREF_ID%TYPE,
  PI_PRREFVER IN CDR_PROGRAM_REFS.PRREF_VER%TYPE,
  PI_TDOBJ IN CDR_NAMING_VERSION_OBJ_TYPE,
  PI_INSTANCESUBTYPEID IN CDR_NAMINGS.OBJECT_SUBTYPE_ID%TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_PRREFID** (Mandatory) Enter the PRREF_ID of the executable object instance—Program, Load Set, Data Mart, OR Business Area instance that owns the Table Descriptors that you want to map. (Use other APIs in this package to get this value.)
- **PI_PRREFVER** (Mandatory) Enter the PRREF_VER of the executable object instance or Business Area instance that owns the Table Descriptors that you want to map. (Use other APIs in this package to get this value.)
- **PI_TDOBJ** (Mandatory) This is a parameter of table type CDR_NAMING_VERSIONS_OBJ_TYPE that contains CDR Naming Version attributes. Enter values for the Table Descriptor from which you want to create a Table Descriptor. The required attributes are: COMPANY_ID, OBJ_ID, OBJ_VER.
- **PI_INSTANCESUBTYPEID** (Mandatory) Enter a value for the Table instance's subtype.

Modify a Mapping Column

Use this API to update a mapping at the Column level. You can map currently unmapped Columns, map Table Descriptor Columns to different Columns in the Table instance, change

the default value for any Column, and supply or change a format string for a Column. This API enforces all Column mapping rules.

Name

CDR_PUB_DF_MAPPING.UpdateMappingColumns

Signature

```
PROCEDURE UPDITEMAPPINGCOLUMNS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_MAPPING_COLUMNS IN CDR_MAPPING_COLUMNS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_MAPPING_COLUMNS (Mandatory) This is a collection of CDR_MAPPING_COLUMNS_TYPES. For each Column that you want to modify, initialize a CDR_MAPPING_COLUMNS_TYPE and then extend the collection. All the attributes are required.

Modify a Mapping at the Table Descriptor Level

Use this API to update a mapping at the Table Descriptor level in accordance with all validation rules.

Name

CDR_PUB_DF_MAPPING.ModifyMapping

Signature

```
PROCEDURE UPDITEMAPPINGCOLUMNS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_MAPPING_COLUMNS IN CDR_MAPPING_COLUMNS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PI_MAPPING_COLUMNS (Mandatory) This is a collection of CDR_MAPPING_COLUMNS_TYPES. For each Column that you want to modify, initialize a CDR_MAPPING_COLUMNS_TYPE and then extend the collection. All the attributes are required.

Get a PRREF_ID for an Executable in a Workflow

Use this API to get the PRREF_ID and PRREF_VER for an executable Object instance contained in a Workflow. You need these values to run Mapping APIs.

Name

CDR_PUB_DF_MAPPING.GetPRREFIDforObjUnderWF

Signature

```
PROCEDURE GETPRREFIDFOROBJUNDERWF(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_SIMPLEOBJ IN CDR_BASE_OBJ_TYPE,
  PI_RSIOBJ IN CDR_BASE_OBJ_TYPE,
  PI_WFIOBJ IN CDR_BASE_OBJ_TYPE,
  PO_PRREFID OUT CDR_PROGRAM_REFS.PRREF_ID%TYPE,
  PO_PRREFVER OUT CDR_PROGRAM_REFS.PRREF_VER%TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_SIMPLEOBJ** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Program, Load Set, or Data Mart instance whose PRREFID you need.
The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER.
- **PI_RSIOBJ** (Optional) If you are getting the PRREFID for a Program instance contained in a Report Set that within a Workflow, enter values to identify the Report Set instance in which the Program instance is located. This is a parameter of table type CDR_BASE_OBJ_TYPE.
The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER.
- **PI_WFIOBJ** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Workflow instance that contains the Program, Load Set, or Data Mart instance whose PRREFID you need.
The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER.
- **PO_PRREFID** This output parameter returns the executable object instance's PRREF_ID.
- **PO_PRREFVER** This output parameter returns the executable object instance's PRREF_VER.

Get a PRREF_ID for an Object in a Work Area

Use this API to get the PRREF_ID and PRREF_VER for a Program, Load Set, Data Mart, or Business Area instance contained directly in a Work Area. You need these values to run Mapping APIs.

Name

CDR_PUB_DF_MAPPING.GetPRREFIDforSimpleObject

Signature

```
PROCEDURE GETPRREFIDFORSIMPLEOBJECT (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_SIMPLEOBJ IN CDR_BASE_OBJ_TYPE,
  PO_PRREFID OUT CDR_PROGRAM_REFS.PRREF_ID%TYPE,
  PO_PRREFVER OUT CDR_PROGRAM_REFS.PRREF_VER%TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_SIMPLEOBJ** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Program, Load Set, Data Mart, or Business Area instance whose PRREFID you need in order to map its Table Descriptors. The following attributes are required: COMPANY_ID,OBJ_ID,OBJ_VER.
- **PO_PRREFID** This output parameter returns the Program, Load Set, Data Mart, or Business Area instance's PRREF_ID.
- **PO_PRREFVER** This output parameter returns the Program, Load Set, Data Mart, or Business Area instance's PRREF_VER.

Get a PRREF_ID for a Program in a Report Set

Use this API to get the PRREF_ID and PRREF_VER for a Program instance contained in a Report Set. You need these values to run Mapping APIs.

Name

CDR_PUB_DF_MAPPING.GetPRREFIDforPgmUnderRSE

Signature

```
PROCEDURE GETPRREFIDFORPGMUNDERRSE (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_SIMPLEOBJ IN CDR_BASE_OBJ_TYPE,
  PI_RSIOBJ IN CDR_BASE_OBJ_TYPE,
  PO_PRREFID OUT CDR_PROGRAM_REFS.PRREF_ID%TYPE,
  PO_PRREFVER OUT CDR_PROGRAM_REFS.PRREF_VER%TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_SIMPLEOBJ** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Program instance whose PRREFID you need in order to map its Table Descriptors.
The following attributes are required: COMPANY_ID,OBJ_ID,OBJ_VER.
- **PI_RSIOBJ** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Report Set instance that contains the Program instance whose PRREFID you need.
The following attributes are required: COMPANY_ID, OBJ_ID AND OBJ_VER.
- **PO_PRREFID** Output Prref_Id
- **PO_PRREFVER** Output Prref Ver

Outputs

This package includes APIs for submitting a job for printing, and for retrieving the BLOB and CLOB objects associated with Oracle LSH output.

This chapter contains the following section:

- [Generate Outputs](#)

Generate Outputs

This section contains the following topics:

- [Submit a Print Request](#)
- [Get an Output's BLOB](#)
- [Get an Output's CLOB](#)

Submit a Print Request

Use this API to print a specified output. The API submits a request to the Oracle LSH printing concurrent program that prints the specified output.

Name

CDR_PUB_PRINT_OUTPUT.SubmitPrintRequest

Signature

```
FUNCTION SUBMITPRINTREQUEST (
  P_API_VERSION IN      NUMBER,
  P_INIT_MSG_LIST IN     VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN           VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN  NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT    VARCHAR2,
  X_MSG_COUNT OUT        NUMBER,
  X_MSG_DATA OUT         VARCHAR2,
  PI_NCOMPANYID IN       CDR_NAMINGS.COMPANY_ID%TYPE,
  PI_NOUTPUTID IN        CDR_NAMINGS.OBJ_ID%TYPE,
  PI_NOUTPUTOBJVER IN     CDR_NAMING_VERSIONS.OBJ_VER%TYPE,
  PI_VPRINTERNAME IN     FND_PRINTER.PRINTER_NAME%TYPE := NULL,
  PI_VCOVERSHEET IN      VARCHAR2 := NULL
) RETURN NUMBER;
```

Return

Type NUMBER

Description Concurrent Request Id

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NCOMPANYID** (Mandatory) Enter your company ID.
To get your company ID, use CDR_DF_PUB_DEF_CONSTANTS.Current_Company_ID.
- **PI_NOUTPUTID** (Mandatory) Enter the obj_id of the output you want to print.
- **PI_NOUTPUTOBJVER** (Mandatory) Enter the obj_ver of the output you want to print.
- **PI_VPRINTERNAME** (Mandatory) Enter the printer name.
- **PI_VCOVERSHEET** (Mandatory) Enter the text for the coversheet. You can enter text only up to 4000 bytes.

Get an Output's BLOB

Use this API to retrieve the BLOB associated with an output object.

Name

CDR_PUB_PRINT_OUTPUT.GetOutPutBlob

Signature

```
FUNCTION GETOUTPUTBLOB(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  PI_NCOMPANYID IN CDR_NAMINGS.COMPANY_ID%TYPE,  
  PI_NOUTPUTID IN CDR_NAMINGS.OBJ_ID%TYPE,  
  PI_NOUTPUTOBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE  
) RETURN BLOB;
```

Return

Type BLOB

Description BLOB

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NCOMPANYID** (Mandatory) Enter your company ID.
To get your company ID, use CDR_DF_PUB_DEF_CONSTANTS.Current_Company_ID.
- **PI_NOUTPUTID** (Mandatory) Enter the obj_ID of the output whose BLOB you want to retrieve.
- **PI_NOUTPUTOBJVER** (Mandatory) Enter the obj_ver of the output whose BLOB you want to retrieve.

Get an Output's CLOB

Use this API to retrieve the CLOB associated with a specified output object.

Name

CDR_PUB_PRINT_OUTPUT.GetOutputCLOB

Signature

```
FUNCTION GETOUTPUTCLOB(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  PI_NCOMPANYID IN CDR_NAMINGS.COMPANY_ID%TYPE,  
  PI_NOUTPUTID IN CDR_NAMINGS.OBJ_ID%TYPE,  
  PI_NOUTPUTOBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE  
) RETURN CLOB;
```

Return

Type CLOB

Description Clob

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NCOMPANYID** (Mandatory) Enter your company ID.
To get your company ID, use CDR_DF_PUB_DEF_CONSTANTS.Current_Company_ID.
- **PI_NOUTPUTID** (Mandatory) Enter the obj_ID of the output whose CLOB you want to retrieve.
- **PI_NOUTPUTOBJVER** (Mandatory) Enter the obj_ver of the output whose CLOB you want to retrieve.

Version Labels

This is a public interface which hosts the Naming API for updating the Version label.

This chapter contains the following section:

- [Modify Version Labels](#)

Modify Version Labels

This section contains one API for updating a version label. See the following topic for details:

- [Update a Version Label](#)

Update a Version Label

Use this API to create or modify an object version label. If the same label exists for another version of the object, the API returns that version number.

Name

CDR_PUB_DF_NAMING.UpdateVersionLabel

Signature

```
PROCEDURE UPDATEVERSIONLABEL (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_NAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **P_API_VERSION** (Mandatory) Enter the current version of the API you are calling. The API compares the version numbers of incoming calls to its current version number and returns an error if they are incompatible.
- **PIO_NAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the object version that you want to label.
The following attributes are required:
COMPANY_ID,OBJ_ID,OBJ_VER,VERSION_LABEL. For VERSION_LABEL enter the text of the label you want to apply to this object version.

Classification

This section contains the following topics:

- [Classify Objects](#)
- [Classify Subtypes](#)
- [Create and Modify Classification Hierarchy Values](#)

Classify Objects

This is a public interface for assigning and removing object classifications.

This section contains the following topics:

- [Classify an Object](#)
- [Declassify an Object](#)

Classify an Object

Use this API to classify Objects

Name

CDR_PUB_CLA_OBJ_CLASSIFICATION.AssignObjectClassification

Signature

```
PROCEDURE ASSIGNOBJECTCLASSIFICATION(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SOURCECDRNAMING IN OUT CDR_NAMING_VERSION_OBJ_TYPE,
  PI_OCLASSIFICATIONS IN CDR_CLASSIFICATIONS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_SOURCECDRNAMING** (Mandatory) This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the object that you want to classify.
The following attributes are required:
COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,
NAMESPACE_OBJ_VER,OBJECT_SUBTYPE_ID.
- **PI_OCLASSIFICATIONS** This is a collection of CDR_CLA_OBJ_TYPES, which have 5 attributes, including CLA_LEVEL_ID and CLASSIFICATION_ID.

If you want the OBJECT to inherit its classifications for a particular level from its parent, enter the classification level ID and, for the CLASSIFICATION_ID, enter 0 (zero).

If you want to explicitly assign one or more terms for a particular level, initialize a CDR_CLA_OBJ_TYPE for each term, entering the classification level ID and, for the CLASSIFICATION_ID, the term ID. The PAR_ attributes are relevant only to Planned Outputs.

If you are not classifying a Planned Output, do not enter any values for them.

If you are classifying a Planned Output and want to use a Parameter with a classification-driven list of values, use the PAR attributes to identify the Parameter you want to use.

Declassify an Object

Use this procedure to remove a single classification value from a defined Object.

Name

CDR_PUB_CLA_OBJ_CLASSIFICATION.Declassify

Signature

```
PROCEDURE DECLASSIFY(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_NOBJECTID IN CDR_NAMINGS.OBJ_ID%TYPE,
  PI_NCLALEVELID IN PLS_INTEGER,
  PI_NCLASSIFICATIONID IN PLS_INTEGER
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NOBJECTID** (Mandatory) Enter the object ID of the object from which you want to remove classifications.)
- **PI_NCLALEVELID** (Mandatory) Enter the ID of the classification hierarchy level that contains the classification value, or term, that you want to remove.
- **PI_NCLASSIFICATIONID** (Mandatory) Enter the ID of the classification value, or term, that you want to remove.

Classify Subtypes

This is a public interface for all Classification functions related to Subtypes.

This section contains the following topics:

- [Get a Subtype Classification Level](#)
- [Get an Object Classification Value](#)
- [Get Child Terms](#)

Get a Subtype Classification Level

Use this API to retrieve all the classification hierarchy levels assigned to an Object Subtype. The function returns a collection of CDR_HIER_LEVEL_VAL_OBJ_TYPE.

Name

CDR_PUB_CLA_SUBTYPES.GetClassificationLevels

Signature

```
FUNCTION GETCLASSIFICATIONLEVELS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PIOBJECTSUBTYPEID IN CDR_OBJECT_SUBTYPES_TL.OBJECT_SUBTYPE_ID%TYPE
) RETURN CDR_HIER_LEVEL_VALUES_COLL;
```

Return

Type CDR_HIER_LEVEL_VALUES_COLL

Description classification levels.

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIOBJECTSUBTYPEID Enter the ID of the Object Subtype whose assigned classification levels you want to retrieve.

Get an Object Classification Value

Use this API to get the classifications assigned to the given object ID and version.

Name

CDR_PUB_CLA_SUBTYPES.GetObjectClaValues

Signature

```
FUNCTION GETOBJECTCLAVALUES (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  POBJECTID IN CDR_OBJ_CLA_MAPPINGS.OBJ_ID%TYPE,
  PIOBJECTSUBTYPEID IN CDR_OBJECT_SUBTYPES_TL.OBJECT_SUBTYPE_ID%TYPE
) RETURN CDR_HIER_LEVEL_VALUES_COLL;
```

Return

Type CDR_HIER_LEVEL_VALUES_COLL

Description Classification values

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **POBJECTID** (Mandatory) Enter the Object Id.
- **PIOBJECTSUBTYPEID** (Mandatory) Enter the Object Subtype Id.

Get Child Terms

Use this API to retrieve some or all of the terms on a particular level that are children of a particular parent term. The function returns a collection of CDR_HIER_LEVEL_VAL_OBJ_TYPES.

Name

CDR_PUB_CLA_SUBTYPES.GetClaHierValues

Signature

```
FUNCTION GETCLAHIERVALUES (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PLEVELIDS IN CDR_OPA_ID_COLL,
  PTERMS IN CDR_OPA_STRING_COLL,
  PDOMAINID IN PLS_INTEGER,
  PCLALEVELID IN CDR_SUBTYPE_CLA_LEVELS.CLA_LEVEL_ID%TYPE
) RETURN CDR_HIER_LEVEL_VALUES_COLL;
```

Return

Type CDR_HIER_LEVEL_VALUES_COLL

Description Classification hierarchy values

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PLEVELIDS** (Mandatory) This is a collection of CDR_OPA_ID_OBJ_TYPES. For each hierarchy level from the top level to the level from which you want to retrieve terms (but not lower), initialize a CDR_OPA_ID_OBJ_TYPE and then extend the collection. The following attribute is required: CDR_OPA_ID.
- **PTERMS** (Mandatory) This is a collection of CDR_OPA_STRING_OBJ_TYPES. For each hierarchy level from the top level to the one from which you want to retrieve terms (but not lower), initialize a CDR_OPA_ID_OBJ_TYPE and then extend the collection. For the required attribute, CDR_OPA_STRING, enter the term whose related terms you want to retrieve, in order starting with the top level.
- **PDOMAINID** Enter the ID of the LSH Instance Domain. Use the following query to get this ID: select * from TMS.TMS_DEF_DOMAINS where name = 'CDR_USER_HIER'
- **PCLALEVELID** Enter the ID of the classification hierarchy level that contains the terms you are searching for.

Create and Modify Classification Hierarchy Values

This is a public interface for classification hierarchy value-related operations.

This section contains the following topics:

- [Insert a Classification Value](#)

- [Update a Classification Value](#)
- [Delete a Classification Value](#)

Insert a Classification Value

Use this API to insert values, or terms, into a classification hierarchy level, related to a term in the next higher level. The function returns 0 if the transaction failed and 1 if it succeeded.

Name

CDR_PUB_CLA_HIERARCHY_VALS.InsertValues

Signature

```
FUNCTION INSERTVALUES (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PPARENTCONTENTID IN TMS.TMS_DICT_CONTENTS.DICT_CONTENT_ID%TYPE,
  PLEVELID IN TMS.TMS_DEF_LEVELS.DEF_LEVEL_ID%TYPE,
  PVALUES IN OUT CDR_HIER_VAL_COLL
) RETURN PLS_INTEGER;
```

Return

Type PLS_INTEGER

- 0 is returned if the transaction fails.
- 1 is returned if the transaction succeeds.

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PPARENTCONTENTID** Enter the ID of a term that serves as a parent to the terms you are inserting.
- **PLEVELID** Enter the ID of the classification hierarchy level into which you want to insert the terms.
- **PVALUES** (Mandatory) This is a collection of CDR_HIER_VAL_TYPES. For each classification value (term) that you want to add as a child to the term you specified, initialize a CDR_HIER_VAL_TYPE and then extend the collection.
The following attributes are required:
CONTENT_ID,TERM,ERROR_MSG,APPROVED_FLAG.

Update a Classification Value

Use this API to modify classification hierarchy values. It returns 1 for transaction success and 0 for failure. It also returns a PVALUES collection that includes error messages for any terms that could not be updated.

Name

CDR_PUB_CLA_HIERARCHY_VALS.UpdateValues

Signature

```

FUNCTION UPDATEVALUES (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PVALUES IN OUT CDR_HIER_VAL_COLL
) RETURN PLS_INTEGER;

```

Return

Type PLS_INTEGER

- 0 is returned if the transaction fails.
- 1 is returned if the transaction succeeds.

PVALUES returns a collection that includes error messages for any terms that could not be updated.

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PVALUES (Mandatory) This is a collection of CDR_HIER_VAL_TYPES. For each classification value (term) that you want to modify, initialize a CDR_HIER_VAL_TYPE and then extend the collection.

The following attributes are required: CONTENT_ID,TERM,APPROVED_FLAG.

You can modify the term itself or its Approved flag value.

Delete a Classification Value

Use this API to delete classification values (terms). The API does not delete terms if they have been assigned as the default value for an object subtype or if they have been assigned to any object. If neither case is true, then the API deletes the term and any related terms it may have lower in the classification hierarchy.

Name

CDR_PUB_CLA_HIERARCHY_VALS.DeleteValues

Signature

```

PROCEDURE DELETEVALUES (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PVALUES IN OUT CDR_HIER_VAL_COLL
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PVALUES (Mandatory) This is a collection of CDR_HIER_VAL_TYPES. For each classification value (term) that you want to delete, initialize a CDR_HIER_VAL_TYPE and then extend the collection.

The following attribute is required: CONTENT_ID.

Job Execution

This section contains the following topics:

- [Create and Execute Output LOBs](#)
- [Retrieve Information about Ongoing Jobs](#)
- [Set Execution Statuses](#)
- [Submit Messages](#)
- [Create Submission Records](#)

Create and Execute Output LOBs

This is a public API for uploading output CLOBs into Oracle LSH. These output CLOBs are generated by Oracle LSH executables outside the Oracle LSH database. For example, a PDF file output from a SAS print program or a SAS CPORT file output from a Data Mart. It also includes APIs that adapters may need to call during the execution of a Load Set, Data Mart, or Program.

This section contains the following topics:

- [Create a Binary Output](#)
- [Upload an Output BLOB](#)
- [Upload an Output CLOB](#)
- [Upload a LOB to a Temporary Table](#)
- [Download a Job Output BLOB](#)
- [Queue a Job](#)
- [Wait for a Job to Complete](#)
- [Generate an XML Payload](#)

Create a Binary Output

Use this API to create a binary output object.

Name

CDR_PUB_EXE_EXTERNAL.CreateBinaryOutput

Signature

```
PROCEDURE CREATEBINARYOUTPUT (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
```

```

X_MSG_DATA OUT    VARCHAR2,
PI_NCOMPANYID IN   NUMBER,
PI_VFILENAME IN    VARCHAR2,
PI_VDATA IN        RAW := NULL
);

```

Parameters

This API has standard parameters (see ["Standard Parameters"](#)) and the following parameters:

- **PI_NCOMPANYID** (Mandatory) Enter Company Id.
- **PI_VFILENAME** (Mandatory) Enter the File Name.
- **PI_VDATA** (Optional) Enter the RAW input to stream up the output.

Upload an Output BLOB

Use this API to upload an output BLOB generated by an external processing engine into Oracle LSH.

Name

CDR_PUB_EXE_EXTERNAL.UploadBlobOutput

Signature

```

PROCEDURE UPLOADBLOOUTPUT (
  P_API_VERSION IN    NUMBER,
  P_INIT_MSG_LIST IN   VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN         VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN    NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT    VARCHAR2,
  X_MSG_COUNT OUT        NUMBER,
  X_MSG_DATA OUT         VARCHAR2,
  PI_NJOBID IN           VARCHAR2,
  PI_VFILENAME IN        VARCHAR2,
  PI_NPRREFID IN         VARCHAR2,
  PIO_BLOBSTREAM IN OUT  BLOB
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NJOBID** (Mandatory) Enter the JOB_ID of the job that generated the output.
- **PI_VFILENAME** (Mandatory) Enter the filename associated with the Planned Output.
- **PI_NPRREFID** (Mandatory) Enter the PRREF_ID of the Oracle LSH executable. This attribute is available from the cdr_jobs_v view.
- **PIO_BLOBSTREAM** (Mandatory) This is a parameter of type BLOB. Enter BLOB to be uploaded.

Upload an Output CLOB

Use this API to upload an output CLOB into Oracle LSH.

Name

CDR_PUB_EXE_EXTERNAL.UploadClobOutput

Signature

```
PROCEDURE UPLOADCLOBOUTPUT (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_NJOBID IN VARCHAR2,
  PI_VFILENAME IN VARCHAR2,
  PI_NPRREFID IN VARCHAR2,
  PIO_CLOBSTREAM IN OUT CLOB
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NJOBID** (Mandatory) Enter the JOB_ID of the job that generated the output.
- **PI_VFILENAME** (Mandatory) Enter the filename associated with the Planned Output.
- **PI_NPRREFID** (Mandatory) Enter the PRREFID of the Oracle LSH executable. This attribute is available from the CDR_JOBS table.
- **PIO_CLOBSTREAM** (Mandatory) Enter the variable name for the CLOB in the database.

Upload a LOB to a Temporary Table

Use this API to upload one or more BLOBs or CLOBs (binary or character large objects) to a temporary table.

Name

CDR_PUB_EXE_EXTERNAL.CreateTempLobs

Signature

```
PROCEDURE CREATETEMPLOBS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_NJOBID IN NUMBER,
  PI_BZIP IN BOOLEAN,
  PI_BLOBNAMES IN CDR_VC_LIST_COLL,
  PI_BLOBENTRIES IN CDR_BLOB_LIST_COLL,
  PI_CLOBNAMES IN CDR_VC_LIST_COLL,
  PI_CLOBENTRIES IN CDR_CLOB_LIST_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NJOBID** (Mandatory) Enter the Job_ID. You can get the Job ID by running CDR_PUB_EXE_RUNTIME.GETCURRENTLYEXECUTINGJOBID.
- **PI_BZIP** Is the input lob in zip format? Enter TRUE or FALSE.
- **PI_BLOBNAMES** This parameter is of type cdr_vc_list_coll which is a collection of varchar2(2000). The varchar contains the BLOB file name.
- **PI_BLOBENTRIES** This parameter is a collection of cdr_blob_list_coll which is a collection of BLOB types. This parameter contains the actual file BLOBs. This is always a collection so even if you are uploading a single CLOB, initialize the collection with that BLOB and pass it here.
- **PI_CLOBNAMES** This parameter is of type cdr_vc_list_coll which is a collection of varchar2(2000). The varchar contains the CLOB file name.
- **PI_CLOBENTRIES** This parameter is a collection of cdr_clob_list_coll which is a collection of CLOB type. This contains the actual file CLOBs. This is always a collection so even if you are uploading a single CLOB, initialize the collection with that CLOB and pass it here.

Download a Job Output BLOB

Use this API to download a job output BLOB.

Name

CDR_PUB_EXE_EXTERNAL.DownloadTempBlob

Signature

```
FUNCTION DOWNLOADTEMPBLOB (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PI_NOBJID IN NUMBER,
  PO_VFILENAME OUT VARCHAR2
) RETURN BLOB;
```

Return

Type BLOB

Description returns the output file as a BLOB.

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NOBJID** (Mandatory) Enter the tmp_blob_id of the job output LOB. You can use the following query to get this ID:

```
SELECT tmp_blob_id FROM cdr_temp_blobs_v WHERE job_id = pi_nJobId;
```
- **PO_VFILENAME** (Mandatory) This Out parameter contains the file name of the downloaded LOB file.

Queue a Job

Use this API to queue the job into a service location for execution.

Name

CDR_PUB_EXE_EXTERNAL.SendJob

Signature

```
PROCEDURE SENDJOB(
  P_API_VERSION IN      NUMBER,
  P_INIT_MSG_LIST IN     VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN          VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN  NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT   VARCHAR2,
  X_MSG_COUNT OUT       NUMBER,
  X_MSG_DATA OUT        VARCHAR2,
  PI_VRECEIVER IN       VARCHAR2,
  PI_NJOBID IN          NUMBER,
  PI_VPAYLOAD IN        VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_VRECEIVER** (Mandatory) Enter the name of the Service Location.
- **PI_NJOBID** (Mandatory) Enter the Job_ID. You can get the Job ID by running CDR_PUB_EXE_RUNTIME.GETCURRENTLYEXECUTINGJOBID.
- **PI_VPAYLOAD** (Mandatory) Enter the actual XML Payload generated by the CDR_PUB_EXE_EXTERNAL.GenerateXMLPayload API.

Wait for a Job to Complete

Use this API to enable synchronous execution so that program control waits for a Job to complete before proceeding with the rest of the logic.

Name

CDR_PUB_EXE_EXTERNAL.WaitForFinalStatus

Signature

```
PROCEDURE WAITFORFINALSTATUS(
  P_API_VERSION IN      NUMBER,
  P_INIT_MSG_LIST IN     VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN          VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN  NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT   VARCHAR2,
  X_MSG_COUNT OUT       NUMBER,
  X_MSG_DATA OUT        VARCHAR2,
  PI_NJOBID IN          NUMBER,
  PI_NTIMEOUT IN        NUMBER,
  PI_NSERVICEINSTANCEID IN  NUMBER
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NJOBID** (Mandatory) Enter the Job ID of the Job in process. The Job_ID is returned by the API CDR_PUB_EXE_SUBMISSION.CREATE SUBMISSION and in the UI.

- **PI_NTIMEOUT** (Mandatory) Enter in seconds, the job completion period before the API times out.
- **PI_NSERVICEINSTANCEID** (Mandatory) Enter the service instance that is processing the job. Get the ID from the `cdr_jobs_v` view using the `Job_Id`.

Generate an XML Payload

Use this API to generate the required XML payload for a job execution.

Name

CDR_PUB_EXE_EXTERNAL.GenerateXmlPayload

Signature

```
FUNCTION GENERATEXMLPAYLOAD (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PI_NJOBID IN NUMBER,
  PI_VJOBTYPE IN VARCHAR2,
  PI_NDOWNLOADCONFIGID IN NUMBER,
  PI_VPROGRAM IN VARCHAR2,
  PI_VWORKDIRECTORY IN VARCHAR2,
  PI_VRUNSCRIPT IN VARCHAR2,
  PI_VOUTPUTPATH IN VARCHAR2,
  PI_VPRIORITY IN VARCHAR2,
  PI_VSCHEMA IN VARCHAR2,
  PI_VUSERID IN VARCHAR2,
  PI_VSUBDIRECTORIES IN CDR_VC_LIST_COLL,
  PI_NSURROGATEJOBID IN CDR_JOBS_V.JOB_ID%TYPE := NULL,
  PI_VTECHTYPE IN VARCHAR2 := NULL,
  PI_NSURROGATEPRREFID IN CDR_JOBS_V.PRREF_ID%TYPE := NULL
) RETURN CLOB;
```

Return

Type CLOB Description Returns the generated XML as a CLOB.

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NJOBID** (Mandatory) Enter the `Job_ID`.
- **PI_VJOBTYPE** (Mandatory) Enter the Job Type—either *tmp* for an internal job or *exe* for a user-executed job
- **PI_NDOWNLOADCONFIGID** (Optional) If the entire job configuration is stored in `cdr_temp_blobs` (against the `Job_ID`), you can enter the ID of the BLOB for the job. Query `CDR_TEMP_BLOBS_V` to get the value. If you do not enter a BLOB ID, enter 0.
- **PI_VPROGRAM** (Mandatory) Enter the command to be executed on the server.
- **PI_VWORKDIRECTORY** (Mandatory) Enter the full path of the root folder in the DP server Home under which the job folder gets created.
- **PI_VRUNSCRIPT** (Mandatory) Enter the name of the main script to be executed for the job.

- **PI_VOUTPUTPATH** (Mandatory) Enter the path where the output will be generated, relative to the work directory/ folder.
- **PI_VPRIORITY** (Mandatory) Enter the job priority. The possible values are the lookup codes in the lookup type 'CDR_JOB_PRIORITIES'.
- **PI_VSCHEMA** (Mandatory) Enter the ID of the ZZ_Schema allocated for the current job. You can query CDR_JOBS_V to get this ID.
- **PI_VUSERID** (Mandatory) Enter the UserId that is executing the job. Use the API CDR_PUB_DEF_FACTORY_SUPPORT.GETUSERID to get this ID.
- **PI_VSUBDIRECTORIES** This is a collection of type CDR_VC_LIST_COLL. Enter the names of subdirectories that should be created under the Job directory in the DP Server.
- **PI_NSURROGATEJOBID** SurrogateJobId. (Optional) Enter the job ID under which the created outputs will be uploaded if it is different from the current job; for example, a master job.
- **PI_VTECHTYPE** (Mandatory) Enter the TechType name being used for the job.
- **PI_NSURROGATEPREFID** SurrogatePrefId(Optional) Enter the ID of the master job for this job, if any.

Retrieve Information about Ongoing Jobs

This is a public interface to retrieve information about an ongoing job.

This section contains the following topics:

- [Get an Ongoing Job ID](#)
- [Get Currently Executing Parameters](#)
- [Get Information About a Job](#)
- [Get Additional Job Information \(Overloaded\)](#)

Get an Ongoing Job ID

Use this API to retrieve the job ID of the job that is currently running.

Name

CDR_PUB_EXE_RUNTIME.GetCurrentlyExecutingJobID

Signature

```
FUNCTION GETCURRENTLYEXECUTINGJOBID(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
) RETURN CDR_JOBS.JOB_ID%TYPE;
```

Return

Type CDR_JOBS.JOB_ID%TYPE

Description the job ID of the job which is executing in the current session.

Parameters

This API has standard parameters. See [Standard Parameters](#)) for details.

Get Currently Executing Parameters

Use this API to retrieve the parameters in use by the job that is currently running.

Name

CDR_PUB_EXE_RUNTIME.GetCurrentlyExecutingParams

Signature

```
FUNCTION GETCURRENTLYEXECUTINGPARAMS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
) RETURN CDR_PARAMETER_VALUES_COLL;
```

Return

Type CDR_PARAMETER_VALUES_COLL

Parameters

This API has standard parameters. See [Standard Parameters](#)) for details.

Get Information About a Job

Use this API to retrieve information about a Job by passing its JOB_ID.

Name

CDR_PUB_EXE_RUNTIME.GetJobInfo

Signature

```
PROCEDURE GETJOBINFO (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_NJOBID IN CDR_JOBS.JOB_ID%TYPE,
  PO_RSUBMISSION_V OUT CDR_SUBMISSIONS_V%ROWTYPE,
  PO_RJOB_V OUT CDR_JOBS_V%ROWTYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NJOBID** (Mandatory) Enter the JOB_ID of the job you want information about. You can get the Job ID by running CDR_PUB_EXE_RUNTIME. Get Currently Executing Job ID.

- **PO_RSUBMISSION_V** This is an output parameter. The API returns the row corresponding to the SUBMISSION_ID associated with the JOB_ID value in CDR_JOBS from the CDR_SUBMISSIONS table.
- **PO_RJOB_V** This is an output parameter. The API returns the row corresponding to the JOB_ID from the CDR_JOBS table.

Get Additional Job Information (Overloaded)

Use this API to retrieve information about a Job, including whether it is a Master job or a Top Level job, by passing its JOB_ID.

Name

CDR_PUB_EXE_RUNTIME.GetJobInfo

Signature

```
PROCEDURE GETJOBINFO(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_NJOBID IN CDR_JOBS.JOB_ID%TYPE,
  PO_RSUBMISSION OUT CDR_SUBMISSIONS%ROWTYPE,
  PO_RJOB OUT CDR_JOBS%ROWTYPE,
  PO_BISTOPLEVELJOB OUT BOOLEAN,
  PO_BISMASTERJOB OUT BOOLEAN
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NJOBID** (Mandatory) Enter the JOB ID.
- **PO_RSUBMISSION** This is an output parameter. The API returns the row corresponding to the SUBMISSION_ID (associated with the JOB_ID value in CDR_JOBS) from the CDR_SUBMISSIONS table.
- **PO_RJOB** This is an output parameter. The API returns the row corresponding to the JOB_ID from the CDR_JOBS table.
- **PO_BISTOPLEVELJOB** This is an output parameter. The API returns "T" if the Job is a Top Level Job.
- **PO_BISMASTERJOB** This is an output parameter. The API returns "T" if the job is a Master job.

Set Execution Statuses

This package contains APIs for setting and retrieving the execution status of Oracle LSH Programs. It also contains APIs for setting output parameters from external tools.

This section contains the following topics:

- [Set a User-specific Completion Status](#)

- [Set a Customized Output Title](#)
- [Set a Customized Output Subtitle](#)
- [Set an Output Parameter](#)
- [Get a Completion Status](#)

Set a User-specific Completion Status

Use this API to set the completion status to a user specified value. Valid status values are: 1 for OK; 2 for OK With Warnings; 3 for Failure.

Name

CDR_PUB_EXE_USER_UTILS.SetCompletionStatus

Signature

```
PROCEDURE SETCOMPLETIONSTATUS(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  X_RETURN_STATUS OUT VARCHAR2,  
  X_MSG_COUNT OUT NUMBER,  
  X_MSG_DATA OUT VARCHAR2,  
  PI_NCOMPLETIONSTATUS IN NUMBER := 1  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_NCOMPLETIONSTATUS (Mandatory) Enter the completion status value. Valid values are 1, 2, or 3.

Set a Customized Output Title

Use this API to set a title for individual RSE outputs.

Name

CDR_PUB_EXE_USER_UTILS.SetCustomOutputTitle

Signature

```
PROCEDURE SETCUSTOMOUTPUTTITLE(  
  P_API_VERSION IN NUMBER,  
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
  X_RETURN_STATUS OUT VARCHAR2,  
  X_MSG_COUNT OUT NUMBER,  
  X_MSG_DATA OUT VARCHAR2,  
  PI_VFILEREF IN CDR_PLANNED_OUTPUTS.FILEREF%TYPE,  
  PI_VVALUE IN VARCHAR2  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_VFILEREFF** (Mandatory) Enter the file reference name of the Planned Output to which you want to assign the title.
- **PI_VVALUE** (Mandatory) Enter the title text.

Set a Customized Output Subtitle

Use this API to set a subtitle for individual RSE outputs.

Name

CDR_PUB_EXE_USER_UTILS.SetCustomOutputSubtitle

Signature

```
PROCEDURE SETCUSTOMOUTPUTSUBTITLE (
  P_API_VERSION IN    NUMBER,
  P_INIT_MSG_LIST IN  VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN       VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN    NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT   VARCHAR2,
  X_MSG_COUNT OUT      NUMBER,
  X_MSG_DATA OUT       VARCHAR2,
  PI_VFILEREFF IN      CDR_PLANNED_OUTPUTS.FILEREFF%TYPE,
  PI_VVALUE IN         VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_VFILEREFF** (Mandatory) Enter the file reference name of the Planned Output to which you want to assign the subtitle.
- **PI_VVALUE** (Mandatory) Enter the subtitle text.

Set an Output Parameter

Use this API to send custom parameters and their values to Oracle LSH from external sources such as SAS. Parameter names and their values passed to this API get added to the cdr_temp_output_params table.

Name

CDR_PUB_EXE_USER_UTILS.SetOutputParams

Signature

```
PROCEDURE SETOUTPUTPARAMS (
  P_API_VERSION IN    NUMBER,
  P_INIT_MSG_LIST IN  VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN       VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN    NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT   VARCHAR2,
  X_MSG_COUNT OUT      NUMBER,
  X_MSG_DATA OUT       VARCHAR2,

```

```

    PI_VPARAMNAME IN CDR_TEMP_OUTPUT_PARAMS.PARAMETER_NAME%TYPE,
    PI_VPARAMVALUE IN CDR_TEMP_OUTPUT_PARAMS.PARAMETER_VALUE%TYPE
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_VPARAMNAME** (Mandatory) Enter the parameter name.
- **PI_VPARAMVALUE** (Mandatory) Enter a value for the parameter.

Get a Completion Status

Use this API to retrieve a completion status value. The completion status value can only be one of the following: 1 for OK; 2 for OK With Warnings; 3 for Failure.

Name

CDR_PUB_EXE_USER_UTILS.GetCompletionStatus

Signature

```

FUNCTION GETCOMPLETIONSTATUS(
    P_API_VERSION IN NUMBER,
    P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
    P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
    P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
) RETURN NUMBER;

```

Return

Type NUMBER

Description Completion Status. The values are 1: OK 2: OK_WITH_WARNINGS 3: FAILURE

Parameters

This API has standard parameters. See [Standard Parameters](#) for details.

Submit Messages

This package contains one API related to the submission of messages. See the following topic for details:

- [Submit a Message](#)

Submit a Message

Use this API to add a submission request to the message queue.

Name

CDR_PUB_EXE_MSG_API.Submit_Message

Signature

```

PROCEDURE SUBMIT_MESSAGE(
    P_API_VERSION IN NUMBER,
    P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,

```

```

P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT VARCHAR2,
X_MSG_COUNT OUT NUMBER,
X_MSG_DATA OUT VARCHAR2,
PI_MSG IN VARCHAR2 := NULL
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_MSG (Mandatory). Enter in XML format, the message that you want to add to the message queue.

Create Submission Records

This package contains procedures to log messages during a job run and to create a submission record.

This section contains the following topics:

- [Start a Job](#)
- [Create a Submission, Get Job ID](#)
- [Create a Submission](#)
- [Add a Job Log](#)

Start a Job

Use this API to start the execution of a job.

Name

CDR_PUB_EXE_SUBMISSION.StartJob

Signature

```

PROCEDURE STARTJOB(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_VEXECSMODE IN VARCHAR2 := 'NONE',
  PI_NJOBID IN CDR_JOBS_V.JOB_ID%TYPE,
  PI_NSTREAMID IN NUMBER := NULL
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_VEXECSMODE** (Mandatory) Enter the mode of execution. There are four possible values: SYNCHRONOUS (start the job and wait for completion), QUEUE (enqueue the job on the LSH queues), DIRECT (directly submit the job to OWB but do not wait), STREAM (The stream ID has to be set if this mode is used).

- **PI_NJOBID** (Mandatory) Enter the Job_ID of the job to be executed.
- **PI_NSTREAMID** Enter the OWB Stream ID. The default value is Null. This parameter is required only if mode=STREAM.

Create a Submission, Get Job ID

Use this API to create a submission before starting the job.

Name

CDR_PUB_EXE_SUBMISSION.CreateSubmission

Signature

```
FUNCTION CREATESUBMISSION(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PIO_OSUBMISSION IN OUT CDR_SUBMISSION_OBJ_TYPE,
  PIO_COSUBDETAILS IN OUT CDR_SUBMISSION_DETAILS_COLL,
  PI_JOBCONTEXTRC IN CDR_JOBS_V.JOB_CONTEXT_RC%TYPE,
  PI_EXECMODE IN VARCHAR2,
  PI_REFRESHSTS IN CDR_JOBS_V.REFRESH_TS%TYPE
) RETURN CDR_JOBS_V.JOB_ID%TYPE;
```

Return

CDR_JOBS_V.JOB_ID%TYPE: The Job ID.

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_OSUBMISSION** (Mandatory) This parameter is of type CDR_SUBMISSION_OBJ_TYPE.
Enter values for the following attributes: COMPANY_ID, EXECUTION_SETUP_OBJ_ID, EXECUTION_SETUP_OBJ_VER, WA_OBJ_ID, MASTER_PREF_ID, MASTER_PREF_VER, ACTIVE_FLAG_RC, SUBMISSION_TYPE_RC.

You can query MASTER_PREF_ID and MASTER_PREF_VER from CDR_PROGRAM_REFS_V with the Object ID and version of the object to be executed as the Pref Obj Id and Pref Obj ver.
- **PIO_COSUBDETAILS** (Mandatory) This parameter is part of a collection of runtime parameters. It is of type CDR_SUBMISSION_DETAILS_COLL. Enter values for the runtime parameters that you want to include in the job submission.
The required attributes are: COMPANY_ID, SUBMISSION_ID, PREF_ID, PREF_VER, PARAMETER_REF_OBJ_ID, PARAMETER_REF_OBJ_VER, PARAMETER_VALUE.
- **PI_JOBCONTEXTRC** (Mandatory) Enter the Job Context.
The possible values are the lookup_codes inside the lookup_type CDR_JOB_CONTEXTS: \$JOBCONTEXT\$BACKCHAIN, \$JOBCONTEXT\$COMPONENT, \$JOBCONTEXT\$SCHEDULED; \$JOBCONTEXT\$SUBMISSION.
- **PI_EXECMODE** (Mandatory) Enter a value for the execution mode. There are 3 possible values: SYNCHRONOUS (start the job and wait for completion), QUEUE (enqueue the job on the LSH queues), DIRECT (directly submit the job to OWB but would not wait).

- **PI_REFRESHTS** (Mandatory) Enter the Refresh timestamp you want to have associated with the job. It is normally 'sysdate,' but if you want to explicitly set a timestamp you can enter it here; for example, for a recovery job.

Create a Submission

This API creates a Submission from the initial Job.

Name

CDR_PUB_EXE_SUBMISSION.CreateSubmission

Signature

```
PROCEDURE CREATESUBMISSION(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_OSUBMISSION IN OUT CDR_SUBMISSION_OBJ_TYPE,
  PIO_COPROGRAMSUBDETAILS IN OUT CDR_SUBMISSION_DETAILS_COLL,
  PIO_COSYSTEMSUBDETAILS IN OUT CDR_SUBMISSION_DETAILS_COLL,
  PI_NOAACCOUNTID IN CDR_SUBMISSIONS.OA_ACCOUNT_ID%TYPE := NULL,
  PI_COSNAPSHOT IN CDR_SNAPSHOT_TABLE_COLL := CDR_SNAPSHOT_TABLE_COLL()
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_OSUBMISSION** Object containing Submission attributes like submission_type_rc, execution_setup_id, master_prref_id etc.
- **PIO_COPROGRAMSUBDETAILS** This is part of submission details which is a collection of runtime parameters.
- **PIO_COSYSTEMSUBDETAILS** This is part of submission details which is a collection of system parameters.
- **PI_NOAACCOUNTID** Enter the OA account ID of the user making the submission.
- **PI_COSNAPSHOT** This is a collection of snapshots attributes like Tables Obj_id, Obj_Ver, source_master_job_Id etc.

Add a Job Log

Use this API to populate the cdr_job_log with the log entry for a given job.

Name

CDR_PUB_EXE_SUBMISSION.AddJobLogEntry

Signature

```
PROCEDURE ADDJOBLOGENTRY(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
```

```
P_VALIDATION_LEVEL IN    NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
X_RETURN_STATUS OUT    VARCHAR2,  
X_MSG_COUNT OUT        NUMBER,  
X_MSG_DATA OUT         VARCHAR2,  
PI_NCOMPANYID IN       CDR_JOB_LOG.COMPANY_ID%TYPE,  
PI_NJOBID IN           CDR_JOB_LOG.JOB_ID%TYPE,  
PI_VLOGENTRY IN        VARCHAR2  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_NCOMPANYID** Enter the Company ID.
- **PI_NJOBID** Enter the Job ID.
- **PI_VLOGENTRY** Enter a Log Entry. This accepts a text message.

Security Policy

This is a public interface for object security-related operations. You need the application role CDR_SECURITY_ADMIN or CDR_DATA_SECURITY_ADMIN to use any of these APIs.

This chapter contains the following section:

- [Create and Modify Security Policies](#)

Create and Modify Security Policies

This section contains the following topics:

- [Create a Subtype](#)
- [Copy a Subtype](#)
- [Modify a Subtype](#)
- [Assign Roles to a Subtype Operation](#)
- [Assign Operations to a Subtype Role](#)
- [Remove a Subtype](#)
- [Create a Role](#)
- [Modify a Role](#)
- [Add a Group Role](#)
- [Get Roles for a User](#)
- [Remove a Role](#)
- [Remove a Group Role](#)
- [Create a User Group](#)
- [Add Users to a Group](#)
- [Remove Users from a Role in a User Group](#)
- [Assign a User Group to an Object](#)
- [Copy a User Group](#)
- [Copy a User Group with its Users](#)
- [Modify a User Group](#)
- [Remove All Group Roles from a User Group](#)
- [Remove All Users in a Group](#)
- [Revoke a User Group From an Object](#)
- [Undo a Revoke a User Group Action](#)
- [Remove a User Group](#)
- [Unassign a User Group From an Object](#)

- [Unassign Roles from an Operation on an Object's Subtype](#)
- [Unassign Operations on an Object Subtype's Role](#)
- [Initialize Access to a Security View](#)
- [Prevent Access to a Security View](#)
- [Get the Resource Timeout Limit](#)
- [Set the Resource Timeout Limit](#)
- [Reset the Resource Timeout Limit](#)

Create a Subtype

Use this API to create a new subtype.

Name

CDR_PUB_SECURITY_PKG.CreateSubtype

Signature

```
PROCEDURE CREATESUBTYPE(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SUBTYPE IN OUT CDR_SUBTYPE_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_SUBTYPE (Mandatory) This is a collection of CDR_USER_GROUPS_OBJ_TYPE that contain attributes related to User Groups.

The required attributes are: NAME,OBJECT_SUBTYPE_ID,OBJECT_TYPE_RC.

Copy a Subtype

Use this API to make a copy of a subtype.

Name

CDR_PUB_SECURITY_PKG.CopySubtype

Signature

```
PROCEDURE COPYSUBTYPE(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
```

```
PI_SUBTYPE IN CDR_SUBTYPE_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_SUBTYPE (Mandatory) This is a parameter of table type CDR_SUBTYPE_OBJ_TYPE that contains information about the subtype.

Modify a Subtype

Use this API to update a subtype.

Name

CDR_PUB_SECURITY_PKG.ModifySubtype

Signature

```
PROCEDURE MODIFYSUBTYPE(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_SUBTYPE IN OUT CDR_SUBTYPE_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_SUBTYPE (Mandatory) This is a parameter of table type CDR_SUBTYPE_OBJ_TYPE that contains information about the object subtype.

Assign Roles to a Subtype Operation

Use this API to assign a role to an operation for a subtype of an object.

Name

CDR_PUB_SECURITY_PKG.AssignRolesToSubtypeOperation

Signature

```
PROCEDURE ASSIGNROLESTOSUBTYPEOPERATION(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_ROLESTOOPR IN OUT CDR_SUBTYPE_OPR_ROLES_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_ROLESTOOPR** (Mandatory) This is a collection of CDR_SUBTYPE_OPR_ROLE_OBJ_TYPE.
- **PI_REPLACEALL** This parameter allows you to choose either replace the role(s) already assigned with a new list of roles or to add new assignments to the existing ones. If you do not specify a value for this parameter, the existing assignments are replaced by default.
 - Set to **T** to unassign all currently assigned roles when the new role is assigned.
 - Set to **F** to retain all currently assigned roles when the new role is assigned.

Assign Operations to a Subtype Role

Use this API to assign an operation to a role of an object subtype.

Name

CDR_PUB_SECURITY_PKG.AssignOprToSubtypeRole

Signature

```
PROCEDURE ASSIGNOPRTOSUBTYPEROLE (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_ROLESTOOPR IN OUT CDR_SUBTYPE_OPR_ROLES_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_ROLESTOOPR (Mandatory) This is a collection of CDR_SUBTYPE_OPR_ROLE_OBJ_TYPE.

Remove a Subtype

Use this API to delete a subtype that is not Active. If objects are assigned to the subtype, you cannot delete it even if it is Inactive.

Name

CDR_PUB_SECURITY_PKG.RemoveSubtype

Signature

```
PROCEDURE REMOVESUBTYPE (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
```

```
X_MSG_COUNT OUT NUMBER,
X_MSG_DATA OUT VARCHAR2,
PI_SUBTYPEID IN CDR_OBJECT_SUBTYPES_B.OBJECT_SUBTYPE_ID%TYPE,
PI_COMPANYID IN CDR_OBJECT_SUBTYPES_B.COMPANY_ID%TYPE,
PI_OBJECTTYPERC IN CDR_OBJECT_SUBTYPES_B.OBJECT_TYPE_RC%TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_SUBTYPEID** (Mandatory) Enter the OBJECT_SUBTYPE_ID of the subtype you want to delete.
- **PI_COMPANYID** (Mandatory) Enter the COMPANY_ID associated with the OBJ_SUBTYPE_ID.
- **PI_OBJECTTYPERC** (Mandatory) Enter the OBJECT_TYPE_RC value for the object type associated with the subtype.

Create a Role

Use this API to create a new Role.

Name

CDR_PUB_SECURITY_PKG.CreateRole

Signature

```
PROCEDURE CREATEROLE(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_ROLE IN OUT CDR_ROLE_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PIO_ROLE (Mandatory) This is a parameter of table type CDR_ROLE_OBJ_TYPE that contains attributes related to a Role.

Required Attributes are: NAME, CODE, OBJECT VERSION NUMBER.

Modify a Role

Use this API to update a Role. You can change the name, description, and Active status of a Role.

Name

CDR_PUB_SECURITY_PKG.ModifyRole

Signature

```
PROCEDURE MODIFYROLE (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_ROLE IN OUT CDR_ROLE_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_ROLE (Mandatory) This is a parameter of table type CDR_ROLE_OBJ_TYPE that contains attributes related to a Role.

Required Attributes are: NAME, CODE, OBJECT VERSION NUMBER (pass 1 for this).

Add a Group Role

Use this API to create roles for a User Group.

Name

CDR_PUB_SECURITY_PKG.AddGrpRoles

Signature

```
PROCEDURE ADDGRPROLES (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_ROLES IN OUT CDR_UG_ROLE_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_ROLES (Mandatory) This is a parameter of table type CDR_UG_ROLE_OBJ_TYPE.

Following attributes are required:

COMPANY_ID, USER_GROUP_ID, ROLE_ID, OBJECT_VERSION_NUMBER

Get Roles for a User

Use this API to retrieve all Roles assigned to a user.

Name

CDR_PUB_SECURITY_PKG.GetRolesForUser

Signature

```
FUNCTION GETROLESFORUSER(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  P_USERID IN VARCHAR2
) RETURN CLOB;
```

Return

Type CLOB

Description CLOB for all roles for given user.

Parameters

This API has standard parameters. See [Standard Parameters](#) for details.

Remove a Role

Use this API to delete a role.

Name

CDR_PUB_SECURITY_PKG.RemoveRole

Signature

```
PROCEDURE REMOVEROLE(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_COMPANYID IN NUMBER,
  PI_ROLEID IN NUMBER
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPANYID** (Mandatory) Enter the COMPANY_ID associated with the Role.
- **PI_ROLEID** (Mandatory) Enter the ROLE_ID of the Role that you want to delete.

Remove a Group Role

Use this API to remove a single Role from a User Group. You can remove all Roles from the User Group at the same time by using the Remove All Group Roles API.

Name

CDR_PUB_SECURITY_PKG.RemoveGrpRoles

Signature

```
PROCEDURE REMOVEGRPROLES (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_ROLES IN CDR_UG_ROLE_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_ROLES (Mandatory) This parameter is of table type CDR_UG_ROLE_OBJ_TYPE that contains information about User Groups and Roles.

Create a User Group

Use this API to create a new User Group.

Name

CDR_PUB_SECURITY_PKG.CreateUserGroup

Signature

```
PROCEDURE CREATEUSERGROUP (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_USERGRP IN OUT CDR_USER_GROUP_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PIO_USERGRP (Mandatory) This is a collection of CDR_USER_GROUPS_OBJ_TYPE that contains attributes related to User Groups.

Required attributes are: USER_GROUP_ID,COMPANY_ID, NAME.

Add Users to a Group

Use this API to add users to a User Group.

Name

CDR_PUB_SECURITY_PKG.AddUserToGrp

Signature

```
PROCEDURE ADDUSERTOGRP (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_USERUGROLES IN OUT CDR_USER_UG_ROLE_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PIO_USERUGROLES (Mandatory) This is a parameter of table type CDR_USER_UG_ROLE_OBJ_TYPE.

Required Attributes are: UG_COMPANY_ID, USER_GROUP_ID, ROLE_ID, USER_ID, ROLE_ID

Remove Users from a Role in a User Group

Use this API to delete users from a Role in a User Group.

Name

CDR_PUB_SECURITY_PKG.RemoveUsersInGrp

Signature

```
PROCEDURE REMOVEUSERSINGRP (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_USERUGROLES IN OUT CDR_USER_UG_ROLE_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_USERUGROLES (Mandatory) This parameter is of table type CDR_USER_UG_ROLE_OBJ_TYPE that contains information about user, User Groups, and Roles.

Assign a User Group to an Object

Use this API to assign a User Group to an object.

Name

CDR_PUB_SECURITY_PKG.AssignUsrGrpToObj

Signature

```
PROCEDURE ASSIGNUSRGRPTOOBJ (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_BASEOBJECTTYPE IN OUT CDR_BASE_OBJ_TYPE,
  PI_CDROBJUGCOLL IN CDR_OBJ_UG_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_BASEOBJECTTYPE** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE.
Provide the basic naming attributes for the object to which you want to assign the User Group. (COMPANY_ID, OBJECT_ID, OBJECT_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_VERSION_NUMBER). Initialize these attributes in CDR_BASE_OBJ_TYPE.
- **PI_CDROBJUGCOLL** (Mandatory) This is a collection of CDR_OBJ_UG_OBJ_TYPE.
Enter User Group details in this parameter.
The following are required parameters:
UG_COMPANY_ID, OBJ_COMPANY_ID, USER_GROUP_ID, OBJ_ID and EXCLUSION_FLAG.

Copy a User Group

Use this API to make a copy of a User Group including its Roles but not its users.

Name

CDR_PUB_SECURITY_PKG.CopyUserGroup

Signature

```
PROCEDURE COPYUSERGROUP (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_USERGRP IN OUT CDR_USER_GROUPS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

- **PIO_USERGRP** (Mandatory) This is a collection of CDR_USER_GROUPS_OBJ_TYPE that contains attributes related to User Groups.

Required attributes are: USER_GROUP_ID, COMPANY_ID, NAME.

Copy a User Group with its Users

Use this API to make a copy of a User Group including its roles and users.

Name

CDR_PUB_SECURITY_PKG.CopyUserGroupWithUsers

Signature

```
PROCEDURE COPYUSERGROUPWITHUSERS (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_USERGRP IN OUT CDR_USER_GROUPS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_USERGRP (Mandatory) This is a collection of CDR_USER_GROUPS_OBJ_TYPE that contains attributes related to User Groups. Enter the attribute values of the user group you want to copy.

Required attributes are: USER_GROUP_ID,COMPANY_ID, NAME.

This parameter does not return any values.

Modify a User Group

Use this API to modify a User Group.

Name

CDR_PUB_SECURITY_PKG.ModifyUserGroup

Signature

```
PROCEDURE MODIFYUSERGROUP (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_USERGRP IN OUT CDR_USER_GROUP_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PIO_USERGRP (Mandatory) This is a collection of CDR_USER_GROUPS_OBJ_TYPE that contains attributes related to User Groups.

Required attributes are: USER_GROUP_ID,COMPANY_ID, NAME.

Remove All Group Roles from a User Group

Use this API to remove all Roles from the User Group.

Name

CDR_PUB_SECURITY_PKG.RemoveAllGrpRoles

Signature

```
PROCEDURE REMOVEALLGRPROLES (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_USERGRPID IN NUMBER,
  PI_COMPANY_ID IN NUMBER
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_USERGRPID** (Mandatory) Enter the numeric ID to identify the User Group. This parameter is of type Number and corresponds to the CDR_UG_ROLES.USER_GROUP_ID%TYPE column.
- **PI_COMPANY_ID** (Mandatory) Enter the Company Id.

Remove All Users in a Group

Use this API to remove all users from a Role in a User Group.

Name

CDR_PUB_SECURITY_PKG.RemoveAllUsersInGrp

Signature

```
PROCEDURE REMOVEALLUSERSINGRP (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_USERUGROLES IN OUT CDR_USER_UG_ROLE_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_USERUGROLES (Mandatory) This parameter is of table type CDR_USER_UG_ROLE_OBJ_TYPE that contains information about users, User Groups, and Roles.

Revoke a User Group From an Object

Use this API to revoke a User Group from an object.

To remove access to an object through an inherited User Group, you must revoke the User Group assignment.

Use Unassign User Group from Object (UNASSIGNUSRGRPFROMOBJ) for User Groups assigned explicitly.)

Name

CDR_PUB_SECURITY_PKG.RevokeUsrGrpFromObj

Signature

```
PROCEDURE REVOKEUSRGRPFROMOBJ(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_BASEOBJECTTYPE IN OUT CDR_BASE_OBJ_TYPE,
  PI_CDROBJUGOBJTYPE IN CDR_OBJ_UG_OBJ_TYPE,
  PO_HASVIEWPERMAFTERREVOKE OUT VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_BASEOBJECTTYPE** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the object from which the User Group is to be revoked.
The following attributes are required:
COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.
- **PI_CDROBJUGOBJTYPE** (Mandatory) This is a parameter of table type CDR_OBJ_UG_OBJ_TYPE that contains information about the object and the User Group.
- **PO_HASVIEWPERMAFTERREVOKE** (Mandatory) Enter appropriate values for this parameter to specify whether view permissions exist after the revoking of the User Group from the object.

Undo a Revoke a User Group Action

Use this API to undo the revoking of a User Group from an object.

Name

CDR_PUB_SECURITY_PKG.UnrevokeUsrGrpFromObj

Signature

```
PROCEDURE UNREVOKEUSRGPRFROMOBJ(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_BASEOBJECTTYPE IN OUT CDR_BASE_OBJ_TYPE,
  PI_CDROBJUGOBJTYPE IN CDR_OBJ_UG_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_BASEOBJECTTYPE** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the object.
The following attributes are required:
COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.
- **PI_CDROBJUGOBJTYPE** (Mandatory) This is a parameter of table type CDR_OBJ_UG_OBJ_TYPE that contains information about the object and the User Group.

Remove a User Group

Use this API to delete a User Group from the system. Once deleted, a User Group cannot be reactivated.

Name

CDR_PUB_SECURITY_PKG.RemoveUserGroup

Signature

```
PROCEDURE REMOVEUSERGROUP(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PIO_USERGRP IN OUT CDR_USER_GROUPS_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

- **PIO_USERGRP** (Mandatory) This is a collection of CDR_USER_GROUPS_OBJ_TYPE that contains attributes related to User Groups.

The required attributes are: USER_GROUP_ID, COMPANY_ID.

Unassign a User Group From an Object

Use this API to unassign a User Group from an object. You can unassign User Groups explicitly assigned to the Object. You have to revoke User Groups that are inherited.

Name

CDR_PUB_SECURITY_PKG.UnassignUsrGrpFromObj

Signature

```
PROCEDURE UNASSIGNUSRGRPFROMOBJ(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_BASEOBJECTTYPE IN OUT CDR_BASE_OBJ_TYPE,
  PI_CDROBJUGOBJTYPE IN CDR_OBJ_UG_OBJ_TYPE,
  PO_HASVIEWPERMAFTERUNASSIGN OUT VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_BASEOBJECTTYPE** (Mandatory) This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the object. The required attributes are COMPANY_ID,OBJ_ID,OBJ_VER,OBJECT_VERSION_NUMBER,NAMESPACE_OBJ_ID,NAMESPACE_OBJ_VER.
- **PI_CDROBJUGOBJTYPE** (Mandatory) This is a parameter of table type CDR_OBJ_UG_OBJ_TYPE that contains information about the object and the User Group.
- **PO_HASVIEWPERMAFTERUNASSIGN** (Mandatory) Enter appropriate values for this parameter to specify whether view permissions exist after unassigning the User Group from the object.

Unassign Roles from an Operation on an Object's Subtype

Use this API to unassign Roles from an Operation on an object's subtype.

Name

CDR_PUB_SECURITY_PKG.UnassignRoleToSubtypeOperation

Signature

```
PROCEDURE UNASSIGNROLETOSUBTYPEOPERATION(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
```

```

X_MSG_DATA OUT VARCHAR2,
PI_STOPROLE IN OUT CDR_SUBTYPE_OPR_ROLE_OBJ_TYPE
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_STOPROLE (Mandatory) This parameter is of table type CDR_SUBTYPE_OPR_ROLE_OBJ_TYPE that contains information about object subtype, Role, and operation.

Unassign Operations on an Object Subtype's Role

Use this API to unassign operations on an object subtype's role.

Name

CDR_PUB_SECURITY_PKG.UnassignOprToSubtypeRole

Signature

```

PROCEDURE UNASSIGNOPRTOSUBTYPE_ROLE (
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT VARCHAR2,
  X_MSG_COUNT OUT NUMBER,
  X_MSG_DATA OUT VARCHAR2,
  PI_STOPROLE IN OUT CDR_SUBTYPE_OPR_ROLE_OBJ_TYPE
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_STOPROLE (Mandatory) This parameter is of table type CDR_SUBTYPE_OPR_ROLE_OBJ_TYPE that contains information about object subtype, Role, and operation.

Initialize Access to a Security View

Use this API to initialize access to a Security View for a certain session, to a specific application user.

The API also checks whether the application user has relevant LSH functional security permission to access the Security View data. If the validation is successful, access permission is granted for a given session.

Name

CDR_PUB_SECURITY_PKG.InitializeAccessToSecView

Return

Boolean

- True: The user has the functional security permission.

- False: The user does not have the functional security permission.

Signature

```
FUNCTION INITIALIZEACCESSSTOSECVIEW(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  P_VIEW_NAME VARCHAR2)
RETURN BOOLEAN;
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

- **P_VIEW_NAME** (Mandatory) Enter the public Security View name you need access for:
 - CDR_PUB_UG_ROLES_V
 - CDR_PUB_USER_UG_ROLES_V
 - CDR_PUB_SUBTYPE_OPR_ROLES_V
 - CDR_PUB_OBJ_UG_V

To access all security views in given session, enter CDR_ALL_PUB_SEC_V.

The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER, OBJECT_VERSION_NUMBER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER.

Prevent Access to a Security View

Use this API to check the functional security permissions of an application user and prevent access to a Security View if the user does not have the required permissions.

Name

CDR_PUB_SECURITY_PKG.uninitializeAccessToSecView

Return

Boolean

- True: The user has the functional security permission.
- False: The user does not have the functional security permission.

Signature

```
FUNCTION UNINITIALIZEACCESSSTOSECVIEW(
  P_API_VERSION IN NUMBER,
  P_INIT_MSG_LIST IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  PIO_BASEOBJECT IN OUT CDR_BASE_OBJ_TYPE,
  PI_COMMENT IN VARCHAR2)
RETURN BOOLEAN;
```

Parameters

This API has standard parameters (see [Standard Parameters](#)).

Get the Resource Timeout Limit

Use this API to get the current session timeout limit for all user database accounts.

Name

CDR_PUB_ResourceLimits.getResourceLimit

Signature

```
PROCEDURE getResourceLimit
(
  p_api_version      IN VARCHAR2
, p_init_msg_list    IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE
, p_commit           IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
, p_validation_level IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
, x_return_status    OUT NOCOPY VARCHAR2
, x_msg_count        OUT NOCOPY NUMBER
, x_msg_data         OUT NOCOPY VARCHAR2
, p_name             IN cdr_db_resource_limits.name%TYPE
, p_value            OUT NOCOPY cdr_db_resource_limits.current_value%TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **P_NAME** (Mandatory) Enter the current value set for the database profile name.
- **P_VALUE** (Mandatory) Shows the current limit.

Set the Resource Timeout Limit

Use this API to set the current session timeout limit for all user database accounts (for example, change the default limit of 24 hours to 8 hours). This parameter has a default of 180 minutes with a minimum of 30 minutes and a maximum of 1440 minutes (24 hours)

Name

CDR_PUB_ResourceLimits.setResourceLimit

Signature

```
PROCEDURE setResourceLimit
(
  p_api_version      IN VARCHAR2
, p_init_msg_list    IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE
, p_commit           IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
, p_validation_level IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
, x_return_status    OUT NOCOPY VARCHAR2
, x_msg_count        OUT NOCOPY NUMBER
, x_msg_data         OUT NOCOPY VARCHAR2
, p_name             IN VARCHAR2
, p_value            IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **P_NAME** (Mandatory) Enter the current value set for the database profile name.

- CONNECT_TIME
- **P_VALUE** (Mandatory) Enter a minimum of 30 minutes and a maximum of 1440 minutes (24 hours). (The default is 180 minutes [24 hours]).

Reset the Resource Timeout Limit

Use this API to reset the current session timeout limit for all user database accounts to the default limit of 24 hours.

Name

CDR_PUB_ResourceLimits.resetResourceLimitToDefault

Signature

```
PROCEDURE resetResourceLimitToDefault
(
  p_api_version      IN VARCHAR2
, p_init_msg_list    IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE
, p_commit           IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE
, p_validation_level IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
, x_return_status    OUT NOCOPY VARCHAR2
, x_msg_count        OUT NOCOPY NUMBER
, x_msg_data         OUT NOCOPY VARCHAR2
, p_name             IN cdr_db_resource_limits.name%TYPE
, p_all              IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **P_NAME** (Mandatory) Enter the current value set for the database profile name.
 - CONNECT_TIME
- **P_ALL** (Mandatory) Enter **T** (to reset all profile limits to the default and ignore the P_NAME setting) or **F** (to reset the limit to default for the specified name).

Validation

This is a public interface for validation-related operations.

This section contains the following topics:

- [Validate Objects](#)
- [Create and Modify Validation Supporting Documents](#)

Validate Objects

This section contains one API for updating the validation status of an object. See the following topic for details:

- [Update an Object's Validation Status](#)

Update an Object's Validation Status

Use this API to update an object's validation status. The API performs a cascade validation on this object and its related objects.

If this object is an instance, the API also validates its source definition. If this object contains other objects with a validation status, the API updates the validation status of all of them; and if they are instances, their source definitions.

The operation fails if any of the underlying definitions are checked out. If you are validating a Report Set, the operation also fails if any of the Program instances in the Report Set have a validation status lower than the one to which the Report Set is being upgraded.

Name

CDR_PUB_VL_VALIDATION.UpdateValStatus

Signature

```
PROCEDURE UPDATEVALSTATUS (
  P_API_VERSION IN      NUMBER,
  P_INIT_MSG_LIST IN    VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT IN          VARCHAR2 := CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER := CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  X_RETURN_STATUS OUT   VARCHAR2,
  X_MSG_COUNT OUT       NUMBER,
  X_MSG_DATA OUT        VARCHAR2,
  PI_VALOBJ IN          CDR_VAL_STATUS_OBJ_TYPE,
  PO_CASCADEDOBJCOLL OUT CDR_BASE_OBJ_COLL,
  PO_ERRORNAMINGCOLL OUT CDR_BASE_OBJ_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_VALOBJ** (Mandatory) This is a parameter of table type CDR_VAL_STATUS_OBJ_TYPE. Enter values to identify the object whose validation status you want to update.
The following attributes are required:
COMPANY_ID,OBJ_ID,OBJ_VER,OBJ_TYPE_RC,VALIDATION_STATUS_RC,OBJECT_VERSION_NUMBER.
- **PO_CASCADEDOBJCOLL** This output parameter is a collection of all the objects whose validation status was updated due to cascading. If this parameter contains a value, the validation update operation succeeded.
- **PO_ERRORNAMINGCOLL** This output parameter is a collection of objects whose validation status could not be updated. If this parameter contains a value, the validation update operation failed.

Create and Modify Validation Supporting Documents

This section contains the following topics:

- [Create a Validation Supporting Document](#)
- [Update a Validation Supporting Document](#)
- [Obsolete a Validation Supporting Document](#)

Create a Validation Supporting Document

Use this API to create a validation supporting document.

Name

CDR_PUB_VL_VALIDATION.CreateValDocument

Signature

```
PROCEDURE CREATEVALDOCUMENT (
P_API_VERSION IN NUMBER
,P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE
,P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE
,P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
,X_RETURN_STATUS OUT NOCOPY VARCHAR2
,X_MSG_COUNT OUT NOCOPY NUMBER
,X_MSG_DATA OUT NOCOPY VARCHAR2
, PI_VALDOCOBJ IN CDR_VAL_DOC_BLOB_OBJ_TYPE
) ;
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_VALDOCOBJ (Mandatory) This is a parameter of type CDR_VAL_DOC_BLOB_OBJ_TYPE.

The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER, DOCUMENT_NAME, DESCRIPTION, FILE_NAME, OS_FILE_PATH, FILE_BLOB, FILE_CONTENT_TYPE.

Update a Validation Supporting Document

You can use this API to upload a new document, change attributes such as its description, or both.

Name

CDR_PUB_VL_VALIDATION.UpdateValDocument

Signature

```
PROCEDURE UPDATEVALDOCUMENT (
P_API_VERSION IN NUMBER
,P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE
,P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE
,P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
,X_RETURN_STATUS OUT NOCOPY VARCHAR2
,X_MSG_COUNT OUT NOCOPY NUMBER
,X_MSG_DATA OUT NOCOPY VARCHAR2
,PI_VALDOCOBJ IN CDR_VAL_DOC_BLOB_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_VALDOCOBJ (Mandatory) This is a parameter of type CDR_VAL_DOC_BLOB_OBJ_TYPE. The following attributes of the document to be updated are required: DOCUMENT_ID, COMPANY_ID, OBJ_ID, OBJ_VER, DOCUMENT_NAME, DOC_STATUS_RC, DOCUMENT_VER, DESCRIPTION, CHANGE_REASON, FILE_ID, FILE_NAME, OS_FILE_PATH, FILE_BLOB, FILE_CONTENT_TYPE, OBJECT_VERSION_NUMBER.

To get the OBJECT_VERSION_NUMBER, enter the following query:

```
select Max(OBJECT_VERSION_NUMBER) from cdr_vl_val_docs_v
where OBJ_ID = <objid> and OBJ_VER = <objver> and DOC_STATUS_RC =
'$VALINFOSTATUS$ACTIVE';
```

Obsolete a Validation Supporting Document

Use this API to remove a validation supporting document.

Name

CDR_PUB_VL_VALIDATION.RemoveValDocument

Signature

```
PROCEDURE REMOVEVALDOCUMENT (
P_API_VERSION IN NUMBER
,P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE ,P_COMMIT IN VARCHAR2
DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE
,P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
,X_RETURN_STATUS OUT NOCOPY VARCHAR2
,X_MSG_COUNT OUT NOCOPY NUMBER
,X_MSG_DATA OUT NOCOPY VARCHAR2
,PI_VALDOCOBJ IN CDR_VAL_DOC_BLOB_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PI_VALDOCOBJ (Mandatory) This is a parameter of type CDR_VAL_DOC_BLOB_OBJ_TYPE.

The following attributes of the document to be obsoleted are required: DOCUMENT_ID, COMPANY_ID, DOCUMENT_VER, OBJECT_VERSION_NUMBER.

To get the OBJECT_VERSION_NUMBER, enter the following query:

```
select Max(OBJECT_VERSION_NUMBER) from cdr_vl_val_docs_v
where OBJ_ID = <objid> and OBJ_VER = <objver> and DOC_STATUS_RC =
'$VALINFOSTATUS$ACTIVE';
```

Part IV

Oracle Life Sciences Data Management Workbench APIs

This part of the Oracle Life Sciences Warehouse API guide contains public APIs included in Oracle Life Sciences Data Management Workbench (Oracle DMW). You can call these APIs from custom programs used in Oracle DMW.

To use these APIs you need to understand defined objects in Oracle LSH. Refer to [Essential Information](#) to know more about running APIs in Oracle LSH. Part 1 includes [Reference Information](#), which contains details about the Standard Parameters required to call APIs.

[Setup Utilities](#) contains information on utility APIs that you can use to get the information and IDs you need, to invoke Oracle DMW APIs.

This section includes the following chapters:

- [Introduction to Oracle DMW APIs](#)
- [Clinical Data Models](#)
- [Codelists](#)
- [Flags, Categories, and Actions](#)
- [Transformations](#)
- [Validation Checks](#)
- [Data Loads](#)

Introduction to Oracle DMW APIs

Oracle DMW is built on top of Oracle LSH and shares the same database and execution engine. Be sure to read the following sections, which apply to Oracle DMW as well as Oracle LSH APIs:

- [Using Application Programming Interfaces](#)
- [Reference Information](#)
- [Setup Utilities](#)

For information on Oracle DMW functionality and structure, see the user documentation, including information on object ownership (namespaces).

**Note:**

- Even though an Oracle DMW Study is an Oracle LSH domain, it has additional attributes and you cannot create a study using the API for creating a domain. The API for creating a study is not public. Create studies in the user interface.
- During its initial development, Oracle DMW was known as DME. Therefore many internal names contain the string `dme`. Think of DME as a synonym for Oracle DMW—just as CDR was the early name for Oracle LSH.

This section includes:

- [Set Up the Study Environment](#)
- [Create or Modify an Expression](#)

Set Up the Study Environment

The program you are writing must call `DME_PUB_INITIALIZATION.SetupAPIStudyEnvironment` before it calls any other Oracle DMW API or uses any public view.

This procedure checks that the study ID and lifecycle value you pass in are valid and then uses those values and the study's partition ID for the lifecycle to set `SYS_CONTEXT` appropriately. Call it again to change the study or lifecycle context. See the following topic for details:

- [Initialize a Study and Lifecycle](#)

Initialize a Study and Lifecycle

Name

`DME_PUB_INITIALIZATION.SetupAPIStudyEnvironment`

Signature

```
PROCEDURE SETUPAPISTUDYENVIRONMENT,
( P_API_VERSION IN NUMBER,   P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE,   P_COMMIT IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE,   P_VALIDATION_LEVEL IN NUMBER DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,   X_RETURN_STATUS OUT NOCOPY VARCHAR2,
  X_MSG_COUNT OUT NOCOPY NUMBER,   X_MSG_DATA OUT NOCOPY VARCHAR2,   PI_COMPANY_ID IN
  NUMBER,   PI_STUDY_ID IN NUMBER,   PI_LIFECYCLE IN VARCHAR2,
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPANY_ID** (Mandatory). Enter COMPANY_ID of Study.
- **PI_STUDY_ID** (Mandatory). Enter OBJ_ID of Study.
- **PI_LIFECYCLE** (Mandatory). Enter Lifecycle context values like \$LIFECYCLE\$DEV, \$LIFECYCLE\$QC or \$LIFECYCLE\$PROD.

Create or Modify an Expression

In Oracle DMW, expressions in both validation checks and transformations are defined in the EXPR_OBJ_TYPE attribute of the DME_MAP_ENTITY_OBJ_TYPE. The EXPR_OBJ_TYPE attribute is of the DME_XFORM_EXPR_OBJ_TYPE object and its required values are:

- **EXPRESSION_ID**: If you are modifying an expression, enter the expression object ID.
- **EXPRESSION_MODE**: Enter one:
 - \$EXPRMODE\$CRITERIA if it is a criteria expression.
 - \$EXPRMODE\$EXPR if it is a column expression.
- **EXPRESSION_TEXT**: Enter the string representation of expression, adhering to the following rules:
 - All the values should be single quoted. Numeric values can be applied without single quotes.
 - The column names should be specified in the following format: {ModelName.TableName.ColumnName}. For example, to specify a condition on the 'AGE' column from 'DM' table in 'Source' data model that AGE should be greater than 30, the expression_text should be passed as: {Source.DM.AGE} > 30
 - To specify a user-defined functions, the package should be available in the view DME_PUB_XFM_EXPR_STATIC_PKGS_V. Refer to the static reference details for the package that contains the function.
- **EXPRESSION_ITEM_COLL** - Use this parameter only if you are calling a function in the expression. This is a parameter of collection type DME_XFORM_EXPR_ITEM_OBJ_COLL which is a table of DME_XFORM_EXPR_ITEM_OBJ_TYPE object type. For each expression_text, the collection must be populated with one record with the following attribute assignments:

```
PARENT_ROW_ID = -1; ROW_ID=0; ROW_POS=1; ITEM_TYPE_RC=' $EXPITEMTYPE$GROUP'
```

If user-defined functions are used in expression_text, the collection should be populated with a separate record for each distinct user-defined function used in expression. The following attributes should be assigned for a record used for the user defined function:

- **PARENT_ROW_ID** = 0;
- **ROW_POS** = 1;

 Note:

The above two values should always be 0 and 1, respectively.

- **ROW_ID** - The row_id must be unique and sequential starting from 1 for each distinct user defined function used in the given expression.
- **ITEM_TYPE_RC** = '\$EXPITEMTYPE\$FUNCTION';

Enter values for the following two attributes from the DME_XFM_EXPR_STATIC_PKGS_V view.

- **ITEM** - Enter the name of the user-defined function.
- **STATIC_REFS** - Enter the function ID corresponding to the function used in expression.

Clinical Data Models

This section contains the following topics:

- [Create and Modify Clinical Data Models](#)
- [Get a Custom Listing Business Area ID for a Model](#)

Create and Modify Clinical Data Models

This is a public interface for clinical data model-related operations, including creating, modifying, and removing models, and checking models in and out. It also includes APIs for adding, modifying, and removing tables and constraints to tables within models.

**Note:**

You can also create tables with columns and constraints within a model by uploading metadata files. See the *Oracle Life Sciences Data Management Workbench User's Guide* for more information.

This section contains the following topics:

- [Create a Study Clinical Data Model](#)
- [Create a Study Clinical Data Model from a Library Model](#)
- [Modify a Model's Name and Description](#)
- [Check Out a Clinical Data Model](#)
- [Check In a Clinical Data Model](#)
- [Undo a Clinical Data Model Checkout](#)
- [Install a Study Clinical Data Model](#)
- [Promote a Clinical Data Model to Quality Control or Production](#)
- [Remove a Clinical Data Model](#)
- [Upgrade a Clinical Data Model to the Latest Library Model Version](#)
- [Copy the Subject and/or Subject/Visit Table](#)
- [Add a Table to a Clinical Data Model](#)
- [Modify Table in Clinical Data Model](#)
- [Remove Table from Clinical Data Model](#)
- [Add a Column to a Table in a Clinical Data Model](#)
- [Modify Column Display Characteristics in a Clinical Data Model Table](#)
- [Modify a Column in a Clinical Data Model Table](#)
- [Remove Column from Clinical Data Model Table](#)

- [Add a Constraint to a Clinical Data Model Table](#)
- [Modify a Constraint in a Clinical Data Model Table](#)
- [Remove Constraint from a Clinical Data Model Table](#)
- [Reorder Columns in a Clinical Data Model Table](#)
- [Display Metadata Differences between Tables](#)
- [Validate the Derived Encoding Date Through TMS](#)
API to validate the TMS Encoding Date.

Create a Study Clinical Data Model

Use this API to create a study clinical data model in a study domain. The model contains no tables. Use [Add a Table to a Clinical Data Model](#) to add tables to the model. You can use this API to create either target models, whose data is populated from other Oracle DMW study models, or input models, whose data is loaded from InForm or from files. However, for input models you must complete the configuration in the user interface.

The procedure returns an S if the model is created successfully. Otherwise it returns an error.

Name

DME_PUB_DF_DATA_MODEL.CreateStudyDataModel

Signature

```
PROCEDURE CreateStudyDataModel
(P_API_VERSION          IN NUMBER,
P_INIT_MSG_LIST         IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT               IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL     IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
PIO_STDYMODOBJ         IN OUT NOCOPY CDR_NAMING_VERSION_OBJ_TYPE,
PIO_DMOBJ              IN OUT CDR_DATA_MODEL_OBJ_TYPE,
PIFILETYPE             IN VARCHAR2,
X_RETURN_STATUS        OUT NOCOPY VARCHAR2,
X_MSG_COUNT            OUT NOCOPY   NUMBER,
X_MSG_DATA             OUT NOCOPY   VARCHAR2,
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_STDYMODOBJ** (Mandatory). This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter values for the following attributes for the new model and its namespace, which is the study domain. To get naming version attribute values for the namespace object, which is the study category domain, see [Get a Naming Version Object](#).
 - **COMPANY_ID** To get your company ID, use CDR_PUB_DEF_FACTORY_UTILS.GetCompanyId.
 - **NAME** Enter a name for the new clinical data model.
 - **NAMESPACE_OBJ_ID** Enter the object ID of the parent study domain.
 - **NAMESPACE_OBJ_VER** Enter the object version of the study domain.
 - **NAMESPACE_START_OBJ_VER** Enter 1
 - **NAMESPACE_END_OBJ_VER** Enter 999999

- **DESCRIPTION** Enter a description for the new clinical data model.
- **OBJECT_TYPE_RC** Enter '\$OBJECTYPES\$DATAMODEL'
- **PIO_DMOBJ** (Mandatory). This is a parameter of type CDR_DATA_MODEL_OBJ_TYPE. Enter values for the following attributes for the new clinical data model. This parameter is used for validation purposes.
 - **DM_NAME** Enter null.
 - **DM_NAMESPACE_OBJ_ID** Enter the object ID of the parent study domain.
 - **DM_DESCRIPTION** Enter null.
 - **DM_TABLE_COLL** Leave blank. To add tables use [Add a Table to a Clinical Data Model](#).
 - **LIBRARY_FLAG_RC** Enter \$YESNO\$NO because this is a study model, not a library model.
 - **MODEL_TYPE_RC**
 - * To create a target model, enter \$MODELTYPE\$TARGET.
 - * To create an input model, enter \$MODELTYPE\$INPUT.
 - **MODEL_SUBTYPE_RC**
 - * If the Model Type is \$MODELTYPE\$TARGET, then Model Subtype is null.
 - * If the Model Type is \$MODELTYPE\$INPUT, then model subtype can be either \$INPUTMODTYPE\$INFORM or \$INPUTMODTYPE\$FILE.
 - **CREATE_BA_FLAG_RC** Enter \$YESNO\$YES to create a Business Area to enable visualizations of data in the model or \$YESNO\$NO.
 - **BA_SCHEMA_NAME** By default, the schema uses the model name. If you want a different schema name, enter it. It must be unique across the DMW instance.
- **PIFILETYPE** (Mandatory). To create a target model or an InForm input model, enter NULL. To create a file-type input model, enter either SAS or TEXT for the type of data files to be loaded. For file-type input models, a value here is required to make the File Watcher Configuration tab appear in the user interface so you can complete the model definition.

Create a Study Clinical Data Model from a Library Model

Use this API to create a study clinical data model in a study domain from a clinical data model in a library. The complete model is copied, including all tables, columns, and constraints. The system maintains a relationship between the library model and the study model. If the library model is modified, you can upgrade the study model to the new version—see [Upgrade a Clinical Data Model to the Latest Library Model Version](#). However, any local changes you have made to the study model are lost.

Name

DME_PUB_DF_DATA_MODEL.CreateStudyDMFromLibDM

Signature

```
PROCEDURE CreateStudyDMFromLibDM
(P_API_VERSION          IN NUMBER,
P_INIT_MSG_LIST         IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT                IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL      IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
```

```
PI_LIBMODOBJ      IN NOCOPY CDR_NAMING_VERSION_OBJ_TYPE,
PI_STDYMODOBJ     IN NOCOPY CDR_NAMING_VERSION_OBJ_TYPE,
PIO_DMOBJ         IN CDR_DATA_MODEL_OBJ_TYPE,
X_RETURN_STATUS   OUT NOCOPY VARCHAR2,
X_MSG_COUNT       OUT NOCOPY   NUMBER,
X_MSG_DATA        OUT NOCOPY   VARCHAR2,
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_LIBMODOBJ** (Mandatory). This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter values for the following attributes for the library model and its namespace, which is the library domain for the therapeutic area or other category. Use CDR_PUB_DEF_FACTORY_SUPPORT.GetNamingObject to get the naming version attributes.
 - **COMPANY_ID** To get your company ID, use CDR_PUB_DEF_FACTORY_UTILS.GetCompanyId.
 - **NAME** Enter a name for the library clinical data model.
 - **NAMESPACE_OBJ_ID** Enter the object ID of the parent library domain.
 - **NAMESPACE_OBJ_VER** Enter the object version of the library domain.
 - **NAMESPACE_START_OBJ_VER** Enter 1
 - **NAMESPACE_END_OBJ_VER** Enter 999999
 - **DESCRIPTION** Enter a description for the library clinical data model.
 - **OBJECT_TYPE_RC** Enter '\$OBJTYPES\$DATAMODEL'
- **PI_STDYMODOBJ** (Mandatory). This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter values for the following attributes for the new study model and its namespace, which is the study domain.
 - **COMPANY_ID** To get your company ID, use CDR_PUB_DEF_FACTORY_UTILS.GetCompanyId.
 - **NAME** Enter a name for the study clinical data model.
 - **NAMESPACE_OBJ_ID** Enter the object ID of the parent study domain.
 - **NAMESPACE_OBJ_VER** Enter the object version of the study domain.
 - **NAMESPACE_START_OBJ_VER** Enter 1
 - **NAMESPACE_END_OBJ_VER** Enter 999999
 - **DESCRIPTION** Enter a description for the study clinical data model.
 - **OBJECT_TYPE_RC** Enter '\$OBJTYPES\$DATAMODEL'
- **PIO_DMOBJ** (Mandatory). This is a parameter of type CDR_DATA_MODEL_OBJ_TYPE. Enter values for the following attributes for the new study clinical data model:
 - **DM_NAME** Enter null.
 - **DM_NAMESPACE_OBJ_ID** Enter the object ID of the parent study domain.
 - **DM_DESCRIPTION** Enter null.
 - **DM_TABLE_COLL** Leave empty. To add tables use [Add a Table to a Clinical Data Model](#).

- **LIBRARY_FLAG_RC** Enter \$YESNO\$NO because this is a study model, not a library model.
- **MODEL_TYPE_RC**
 - * To create a target model, enter \$MODELTYPE\$TARGET.
 - * To create an input model, enter \$MODELTYPE\$INPUT.
- **MODEL_SUBTYPE_RC**
 - * If the model type is \$MODELTYPE\$TARGET, then model subtype is null.
 - * If the model type is \$MODELTYPE\$INPUT, then model subtype can be either \$INPUTMODTYPE\$INFORM or \$INPUTMODTYPE\$FILE.
- **CREATE_BA_FLAG_RC** Enter \$YESNO\$YES to create a Business Area to enable visualizations of data in the model or \$YESNO\$NO.
- **BA_SCHEMA_NAME** By default, the schema uses the model name. If you want a different schema name, enter it. It must be unique across the DMW instance.

Modify a Model's Name and Description

Use this API to modify a study clinical data model's name and description.

Name

DME_PUB_DF_DATA_MODEL.ModifyStudyDataModel

Signature

```
PROCEDURE ModifyStudyDataModel
(P_API_VERSION          IN NUMBER,
P_INIT_MSG_LIST         IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT               IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL     IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
PIO_STDYMODOBJ         IN OUT NOCOPY CDR_NAMING_VERSION_OBJ_TYPE,
PIO_DMOBJ              IN OUT CDR_DATA_MODEL_OBJ_TYPE,
X_RETURN_STATUS        OUT NOCOPY VARCHAR2,
X_MSG_COUNT            OUT NOCOPY NUMBER,
X_MSG_DATA             OUT NOCOPY VARCHAR2,
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_STDYMODOBJ** (Mandatory). This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter values for the new name and description.
- **PIO_DMOBJ** (Mandatory). This is a parameter of type CDR_DATA_MODEL_OBJ_TYPE. Enter values for the following attributes for the new clinical data model:
 - **DM_NAME** Enter a name for the model.
 - **DM_NAMESPACE_OBJ_ID** Enter the object ID of the study or library domain.
 - **DM_DESCRIPTION** Enter a description for the model.
 - **DM_TABLE_COLL** Leave empty. To add tables see [Add a Table to a Clinical Data Model](#).
 - **LIBRARY_FLAG_RC** Enter \$YESNO\$NO if this is a study model or \$YESNO\$YES if it is a library model.

- **MODEL_TYPE_RC** Enter the value for the model: \$MODELTYPE\$TARGET or \$MODELTYPE\$INPUT.
- **MODEL_SUBTYPE_RC** Enter the model's subtype:
If the model type is \$MODELTYPE\$TARGET, then model subtype is null.

If the model type is \$MODELTYPE\$INPUT, then model subtype can be either \$INPUTMODTYPE\$INFORM or \$INPUTMODTYPE\$FILE.
- **CREATE_BA_FLAG_RC** Enter \$YESNO\$YES to create a Business Area to enable visualizations of data in the model or \$YESNO\$NO.
- **BA_SCHEMA_NAME** By default, the schema uses the model name. If you want a different schema name, enter it. It must be unique across the DMW instance.
- **PIFILETYPE** (Mandatory). If you are modifying a target model or an InForm input model, enter NULL. If you are modifying a file-type input model, enter either SAS or TEXT.

Check Out a Clinical Data Model

Use this API to check out a study or library clinical data model.

Name

DME_PUB_DF_DATA_MODEL.CheckoutDataModel

Signature

```
procedure CheckoutDataModel(
  p_api_version IN NUMBER
  p_init_msg_list      IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  p_commit             IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  p_validation_level    IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
  pio_naming           IN OUT NOCOPY cdr_naming_version_obj_type,
  pi_comment           IN VARCHAR2,
  x_return_status      OUT NOCOPY VARCHAR2,
  x_msg_count          OUT NOCOPY NUMBER,
  x_msg_data           OUT NOCOPY VARCHAR2);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory). This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter attributes for the clinical data model you are checking out.
- **PI_COMMENT** Enter a checkout comment.

Check In a Clinical Data Model

Use this API to check in a study or library clinical data model.

Name

DME_PUB_DF_DATA_MODEL.CheckinDataModel

Signature

```
procedure CheckinDataModel(
  p_api_version IN NUMBER,
```

```

p_init_msg_list IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
p_commit IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
p_validation_level IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
pio_naming IN OUT NOCOPY cdr_naming_version_obj_type
pi_comment IN VARCHAR2
x_return_status OUT NOCOPY VARCHAR2
x_msg_count OUT NOCOPY NUMBER
x_msg_data OUT NOCOPY VARCHAR2);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory). This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter attributes for the clinical data model you are checking in.
- **PI_COMMENT** Enter a checkin comment.

Undo a Clinical Data Model Checkout

Use this API to undo the checkout of a study or library clinical data model.

Name

DME_PUB_DF_DATA_MODEL.UncheckoutModel

Signature

```

PROCEDURE UncheckoutModel(
  p_api_version          IN NUMBER
  p_init_msg_list        IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  p_commit               IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  p_validation_level      IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
  pio_naming              IN OUT NOCOPY cdr_naming_version_obj_type
  x_return_status        OUT NOCOPY VARCHAR2
  x_msg_count            OUT NOCOPY NUMBER
  x_msg_data             OUT NOCOPY VARCHAR2);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory). This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter attributes for the clinical data model for which you are undoing the checkout.

Install a Study Clinical Data Model

Use this API to install a study clinical data model.

Name

DME_PUB_DF_DATA_MODEL.DeployStudyDataModel

Signature

```

procedure DeployStudyDataModel(
  p_api_version IN NUMBER
  p_init_msg_list IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  p_commit IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE

```

```
p_validation_level    IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
x_return_status OUT NOCOPY VARCHAR2
x_msg_count OUT NOCOPY NUMBER
x_msg_data OUT NOCOPY VARCHAR2
pi_StudyModObj IN OUT NOCOPY cdr_naming_version_obj_type
pi_Context IN VARCHAR2);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_STUDYMODOBJ** (Mandatory): This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter attributes for the clinical data model that you are installing.
- **PI_CONTEXT** (Mandatory): Enter the lifecycle area in which you are installing the clinical data model:
 - '\$LIFECYCLE\$DEV'
 - '\$LIFECYCLE\$PROD'
 - '\$LIFECYCLE\$QC'

Promote a Clinical Data Model to Quality Control or Production

Use this API to promote a study clinical data model to either the Quality Control or Production validation status.

Name

DME_PUB_DF_DATA_MODEL.UpdateValStatus

Signature

```
PROCEDURE updateValStatus(
  p_api_version      IN NUMBER
  p_init_msg_list    IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  p_commit           IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  p_validation_level IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
  pio_naming         in out nocopy cdr_naming_version_obj_type
  x_return_status    OUT NOCOPY VARCHAR2
  x_msg_count        out nocopy number
  x_msg_data         OUT NOCOPY VARCHAR2);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **P_VALIDATION_LEVEL**
- **PIO_NAMING** (Mandatory): This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter attributes for the clinical data model that you are promoting.
- **PIO_NAMING.VALIDATION_STATUS_RC** (Mandatory): Enter the validation status to which you are promoting the clinical data model:
 - '\$SYSVALDNSTEPS\$DEVELOPMENT'
 - '\$SYSVALDNSTEPS\$QUALITYCONTROL'
 - '\$SYSVALDNSTEPS\$PRODUCTION'

Remove a Clinical Data Model

Use this API to delete a study clinical data model.

Name

DME_PUB_DF_DATA_MODEL.RemoveStudyDataModel

Signature

```
Procedure RemoveStudyDataModel(  
  p_api_version IN NUMBER  
  p_init_msg_list IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE  
  p_commit IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE  
  p_validation_level IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL  
  pio_StdyModObj IN OUT NOCOPY cdr_naming_version_obj_type  
  x_return_status OUT NOCOPY VARCHAR2  
  x_msg_count OUT NOCOPY NUMBER  
  x_msg_data OUT NOCOPY VARCHAR2);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_STDYMODOBJ (Mandatory): This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter attributes for the clinical data model that you are removing.

Upgrade a Clinical Data Model to the Latest Library Model Version

Use this API to upgrade a study clinical data model that was created from a library model to the latest version of the library model.

Name

DME_PUB_DF_DATA_MODEL.UpgradeSDMToLatestLDM

Signature

```
PROCEDURE UpgradeSDMToLatestLDM(p_api_version          IN NUMBER  
  p_init_msg_list      IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE  
  p_commit              in varchar2 default cdr_pub_def_constants.g_false  
  p_validation_level    in number default cdr_pub_def_constants.g_valid_level_full  
  pio_StdyModObj        IN OUT NOCOPY  cdr_naming_version_obj_type  
  x_return_status        OUT NOCOPY VARCHAR2  
  x_msg_count           OUT NOCOPY NUMBER  
  x_msg_data            OUT NOCOPY VARCHAR2);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_STDYMODOBJ (Mandatory): This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter attributes for the clinical data model that you are upgrading.

Copy the Subject and/or Subject/Visit Table

Use this API to copy the SUBJECT table, the SUBJECT/VISIT table, or both tables from a library data model or from the shipped default structures.

Name

DME_PUB_DF_DATA_MODEL.Copy_Subj_Vist_From_Lib

Signature

```
procedure copy_subj_vist_from_lib(  
  p_api_version          IN NUMBER  
  p_init_msg_list        IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE  
  p_commit               in varchar2 default cdr_pub_def_constants.g_false  
  p_validation_level     in number default cdr_pub_def_constants.g_valid_level_full  
  pilibmod              in cdr_naming_version_obj_type  
  pitgtstdymod          in cdr_naming_version_obj_type  
  piCopySel             IN VARCHAR2  
  x_return_status out nocopy varchar2  
  x_msg_count         out nocopy number  
  x_msg_data          out nocopy varchar2);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PILIBMOD** (Mandatory): Enter values for the library model from which you want to copy the tables, if any. This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE.
 - To copy from a library data model, enter attribute values for the library data model.
 - To copy default table structures, enter null values.
- **PITGTSTDYMOD** (Mandatory): Enter values for the study clinical data model **into which** you want to copy one or both tables. This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE.
- **PICOPYSEL** (Mandatory) Specify which table(s) to copy:
 - SUB to copy the Subject table only.
 - VIS to copy the Subject/Visit table only.
 - BOTH to copy both tables.

Add a Table to a Clinical Data Model

Use this API to add a table to clinical data model. The table is created without columns or constraints. To add columns, see [Add a Column to a Table in a Clinical Data Model](#). To add constraints, see [Add a Constraint to a Clinical Data Model Table](#). Note that you can create a table with columns and constraints by uploading a metadata file through the user interface. See *Oracle Life Sciences Data Management Workbench User's Guide* for more information.

Name

DME_PUB_DF_DATA_MODEL.AddTableToDataModel

Signature

```
Procedure AddTableToDataModel (
  p_api_version      IN NUMBER
  p_init_msg_list     IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  p_commit           IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  p_validation_level  IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
  x_return_status     OUT NOCOPY VARCHAR2
  x_msg_count        OUT NOCOPY NUMBER
  x_msg_data         OUT NOCOPY VARCHAR2
  pio_naming         IN OUT NOCOPY      cdr_naming_version_obj_type
  pio_table          IN OUT NOCOPY      cdr_dm_table_obj_type
  pi_defClassificationColl IN CDR_CLASSIFICATIONS_COLL);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory): Enter values for the study clinical data model to which you want to add a table. This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE.
 - **COMPANY_ID** Company ID of the Data Model.
 - **OBJECT_TYPE_RC** Enter \$OBJTYPES\$TABLE.
 - **NAME** Name of the Table.
 - **NAMESPACE_OBJ_ID** Object ID of the Model.
 - **NAMESPACE_OBJ_VER** Object Version of the Model.
 - **DESCRIPTION** Description of the Table.
- **PIO_TABLE** (Mandatory): Enter values for the table:
 - **COMPANY_ID** To get your company ID, use CDR_PUB_DEF_FACTORY_UTILS.GetCompanyId.
 - **ORACLE_NAME**: Enter an Oracle name.
 - **SAS_NAME**: Enter a SAS name.
 - **SAS_LABEL**: Enter a SAS label.
 - **SAS_V6_FLAG_RC**: If you are using SAS version 6, enter '\$YESNO\$YES'. If you are using a more recent version, enter '\$YESNO\$NO'.
 - **AUDIT_TABC_COMPANY_ID, AUDIT_TABC_OBJ_ID, AUDIT_TABC_OBJ_VER**: Leave these three blank.
 - **SNAPSHOT_FLAG_RC**: To allow creating snapshots on this table, enter '\$YESNO\$YES'. To prevent creating snapshots on this table, enter '\$YESNO\$NO'.
 - **PROCESS_TYPE_RC**: Enter '\$PROCESSTYPES\$STAGINGWAUDIT'. This is the required type for newly created tables in Oracle DMW.
 - **BLINDING_FLAG_RC**: If this table may ever contain sensitive data that should be blinded or masked, enter '\$YESNO\$YES'. If not, enter '\$YESNO\$NO'.
 - **REQUIRED_FLAG_RC**: Enter '\$YESNO\$YES' or '\$YESNO\$NO'. This value is not used by the system.
 - **DM_TAB_COL_COLL**: Pass all null values to this collection. To add columns to the table, see [Add a Column to a Table in a Clinical Data Model](#).

- **DM_TAB_CONS_COLL**: Pass all null values to this collection. To add constraints to the table, see [Add a Constraint to a Clinical Data Model Table](#).
- **STAGING_FLAG_RC**: If this is a temporary staging table required for use in a transformation, enter '\$YESNO\$YES'. Otherwise enter '\$YESNO\$NO'.
- **USABLE_FLAG_RC**: Enter '\$YESNO\$YES' or '\$YESNO\$NO'. This value is not used by the system.
- **IDENTIFIER_TAB_COMP_ID**: If you are assigning an SDTM ID to the table, enter the company ID of SDTM identifier. To find this and related values, query public view DME_SDTM_TAB_IDENTIFIERS_V.
- **IDENTIFIER_TAB_OBJ_ID**: If you are assigning an SDTM ID to the table, enter the object ID of SDTM identifier.
- **IDENTIFIER_TAB_OBJ_VER**: If you are assigning an SDTM ID to the table, enter the object version of SDTM identifier.
- **BLINDING_CRITERIA**: If the table has row-level blinding (set in the MASKING_TYPE_RC attribute below), enter the blinding criteria as a SQL expression.
- **ALIASES**: Enter one or more alternate names for the column in a comma-separated list with no spaces, for use in automapping transformations.
- **INFORM_REF_PATH_NAME**: Leave blank.
- **MASKING_TYPE_RC**: If the table's BLINDING_FLAG_RC is set to '\$YESNO\$NO', enter '\$MASKING_TYPE\$NONE'.
If the table's BLINDING_FLAG_RC is set to '\$YESNO\$YES', specify the type of blinding: '\$MASKING_TYPE\$COLUMN', '\$MASKING_TYPE\$ROW', or '\$MASKING_TYPE\$TABLE'.
- **BLINDING_CRITERIA_EXPR_ID**: Enter null.
- **BLINDING_CRITERIA_EXPRESSION**: This is a parameter of type DME_XFORM_EXPRESSION_OBJ_TYPE. Enter details for the blinding criteria: EXPRESSION_ID: Enter null (to create a new expression ID).

POSITION: Position of component.

COMPONENT_TYPE_RC: Enter '\$EXPCOMPTYPE\$OPERATOR' or '\$EXPCOMPTYPE\$CONSTANT'

COMPONENT: Enter component STATIC_REFS: If the expression references an existing function, enter the function ID.

For example, the expression:

```
BLINDING_CRITERIA= 'ADDN_TABL1.DEPTNO>0';
```

has three components:

```
"ADDN_TABL1.DEPTNO"
">"
"0"
```

To create a collection of type DME_XFORM_EXPRESSION_OBJ_TYPE with these components:

```
oExprType :=DME_XFORM_EXPRESSION_OBJ_TYPE(NULL,1,'$EXPCOMPTYPE$CONSTANT','ADDN_TABL1.DEPTNO',NULL);
oExprColl.extend;
oExprColl(oExprColl.last):=oExprType;

oExprType :=DME_XFORM_EXPRESSION_OBJ_TYPE(NULL,2,'$EXPCOMPTYPE$OPERATOR','>',NULL);
```

```
oExprColl.extend;
oExprColl(oExprColl.last):=oExprType;
oExprType                :=DME_XFORM_EXPRESSION_OBJ_TYPE(NULL,3,'$EXPCOMPTYPE$CON
STANT','0',NULL);

oExprColl.extend;
oExprColl(oExprColl.last)      :=oExprType;

BLINDING_CRITERIA_EXPR_COLL:=oExprColl;
```

– **UOW_PROCESS_TYPE_RC:**

If programs writing to the table do not use Unit of Work processing, it uses Reload processing. Enter '\$UOWPROCTYPES\$NONUOW'.

If programs writing to the table use Subject Visit Unit of Work processing, enter '\$UOWPROCTYPES\$SUBJ_VISIT'.

If programs writing to the table use Subject Unit of Work processing, enter '\$UOWPROCTYPES\$SUBJ'.

- **PI_DEFCLASSIFICATIONCOLL:** This is a parameter of type CDR_CLASSIFICATIONS_COLL. Pass all null values to this collection.

Modify Table in Clinical Data Model

Use this API to modify a table in a study or library clinical data model.

Name

DME_PUB_DF_DATA_MODEL.ModifyTableInDataModel

Signature

```
procedure ModifyTableInDataModel(
    p_api_version          IN NUMBER
    p_init_msg_list        IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
    p_commit                IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
    p_validation_level      IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
    x_return_status         OUT NOCOPY VARCHAR2
    x_msg_count             OUT NOCOPY NUMBER
    x_msg_data              OUT NOCOPY VARCHAR2
    pio_naming              IN OUT NOCOPY cdr_naming_version_obj_type
    pio_table               IN OUT NOCOPY cdr_dm_table_obj_type );
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_NAMING (Mandatory): Enter current or modified values for the table as required. This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE.

Remove Table from Clinical Data Model

Use this API to remove a table from a study or library clinical data model.

Name

DME_PUB_DF_DATA_MODEL.RemoveTablesInDataModel

Signature

```
procedure RemoveTablesInDataModel(
  p_api_version      IN NUMBER,
  p_init_msg_list     IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE,
  p_commit           IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE,
  p_validation_level  IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  x_return_status     OUT NOCOPY VARCHAR2,
  x_msg_count         OUT NOCOPY NUMBER,
  x_msg_data         OUT NOCOPY VARCHAR2,
  pi_naming_coll IN cdr_naming_list_coll);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_NAMING_COLL (Mandatory): Enter values to identify the table to be removed. This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE.

Add a Column to a Table in a Clinical Data Model

Use this API to add a column to a table in a clinical data model.

Name

DME_PUB_DF_DATA_MODEL.AddColumnToDataModelTab

Signature

```
procedure AddColumnToDataModelTab(
  p_api_version      IN NUMBER
  p_init_msg_list     IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  p_commit           IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  p_validation_level  IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
  x_return_status     OUT NOCOPY VARCHAR2
  x_msg_count         OUT NOCOPY NUMBER
  x_msg_data         OUT NOCOPY VARCHAR2
  pio_naming          IN OUT NOCOPY cdr_naming_version_obj_type
  pio_variable        IN OUT NOCOPY cdr_var_obj_type
  pio_column          IN OUT NOCOPY cdr_dm_column_obj_type );
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter values for the column and its namespace, the table. Six attributes are required:
 - **COMPANY_ID** Company ID of the Table.
 - **OBJECT_TYPE_RC** Enter \$OBJTYPES\$COLUMN.
 - **NAME** Name of the column.
 - **NAMESPACE_OBJ_ID** Object ID of the Table.
 - **NAMESPACE_OBJ_VER** Object Version of the Table.
 - **DESCRIPTION** Description of the column.
- **PIO_VARIABLE** (Mandatory): This is a parameter of type CDR_VAR_OBJ_TYPE. Column objects are based on variable objects. Enter values as follows:

- **COMPANY_ID** To get your company ID, use `CDR_PUB_DEF_FACTORY_UTILS.GetCompanyId`.
- **ORACLE_NAME**: Enter an Oracle name for the column.
- **ORACLE_DATATYPE_RC**: Specify the data type. Enter one:
'\$ORADATATYPES\$VARCHAR2', '\$ORADATATYPES\$DATE', or '\$ORADATATYPES\$NUMBER'
- **LENGTH**:
For Date data type columns, no length is required.
For VARCHAR2 data type columns, the value must be between 1 and 4000.
For Number data type columns, the maximum value is 38.
- **PRECISION**: If the column is of data type Number, enter the precision.
- **SAS_V6_NAME**: Enter a name that conforms to SAS V6 requirements, if needed.
- **SAS_V8_NAME**: Enter a name that conforms to SAS V8 requirements, if needed.
- **SAS_LABEL**: Enter a SAS label, up to 200 characters.
- **SAS_FORMAT**: Enter a SAS format or leave blank to default to the value you entered for LENGTH preceded by a dollar sign (\$).
- **NULLABLE_FLAG_RC**: If null values are allowed in the column, enter '\$YESNO\$YES'. If not (the column is mandatory) enter '\$YESNO\$NO'.
- **DEFAULT_VALUE**: Enter NULL or, if the column should always have a particular data value, enter the value.
- **PIO_COLUMN**: This is a parameter of type `CDR_DM_COLUMN_OBJ_TYPE`. Some attributes are the same as for the variable parameter `PIO_VARIABLE`. The following attributes are required: `COMPANY_ID`, `OBJ_ID`, `OBJ_VER`, `POSITION`, `SAS_LABEL`, `NULLABLE_FLAG_RC`. Enter the same values you did for the variable. In addition:
 - **OBJ_ID** and **OBJ_VER**: Enter NULL.
 - **POSITION**: Enter the column's position in the table relative to other columns.
 - **REQUIRED_FLAG_RC**: Enter the opposite value that you entered for Nullable in the Variable parameter.
 - **NULLABLE_FLAG_RC**: Enter the same value that you entered for Nullable in the Variable parameter.
 - **CODE_LIST_COMPANY_ID**: To associate the column with a codelist, enter the company ID of the codelist. To find this and related values, query public view `DME_PUB_CODELIST_V`.
 - **CODE_LIST_OBJ_ID**: To associate the column the column with a codelist, enter the object ID of the codelist.
 - **CODE_LIST_OBJ_VER**: To associate the column the column with a codelist, enter the object version of the codelist.
 - **IDENTIFIER_VAR_COMP_ID**: If you are assigning an SDTM ID to the column, enter the company ID of SDTM identifier. To find this and related values, query public view `DME_SDTM_COL_IDENTIFIERS_V`.
 - **IDENTIFIER_VAR_OBJ_ID**: If you are assigning an SDTM ID to the column, enter the object ID of SDTM identifier.
 - **IDENTIFIER_VAR_OBJ_VER**: If you are assigning an SDTM ID to the column, enter the object version of SDTM identifier.

- **USABLE_FLAG_RC**: Enter '\$YESNO\$YES' or '\$YESNO\$NO'. This value is not used by the system.
- **MAPPABLE_FLAG_RC**: Enter '\$YESNO\$YES' if the column can be mapped to a source column in a transformation. Internal columns such as CDR\$DUP_NUM and CDR\$KEY should have the value '\$YESNO\$NO'.
If set to '\$YESNO\$NO', the system ignores the column when calculating mapping completeness and when automapping.
- **MASKING_VALUE**: If the column belongs to a table with column-level blinding and should be blinded, enter the masking value.
- **MASKING_CRITERIA**: If the column data values should be masked only in some rows, enter the masking criteria as a SQL expression.
- **SOURCE_KEY_FLAG_RC**: Enter null.
- **ALIASES**: Enter one or more alternate names for the column in a comma-separated list with no spaces, for use in automapping transformations.
- **INFORM_REF_PATH_NAME**: Leave blank.
- **MASKING_LEVEL_RC**: Specify the masking level for the column: , '\$MASKING_LEVEL\$NONE', '\$MASKING_LEVEL\$COLUMN', or '\$MASKING_LEVEL\$CELL'.
- **MASK_VALUE_EXPR_ID**: To use a predefined expression to generate masking values, enter the expression's object ID.
- **MASK_VALUE_EXPRESSION**: If Masking Value is '\$MASKING_LEVEL\$NONE' then pass NULL values. For others pass expression details to parameter DME_XFORM_EXPR_OBJ_TYPE type; see [Add a Table to a Clinical Data Model](#) parameter [BLINDING_CRITERIA_EXPRESSION](#).
- **MASK_CRITERIA_EXPR_ID**: To use a predefined expression to determine which cells to mask, enter the expression's object ID.
- **MASK_CRITERIA_EXPRESSION**: If Masking value is '\$MASKING_LEVEL\$COLUMN' or '\$MASKING_LEVEL\$NONE' then pass the NULL values. For '\$MASKING_LEVEL\$CELL' pass criteria expression details to parameter DME_XFORM_EXPR_OBJ_TYPE type; see [Add a Table to a Clinical Data Model](#) parameter [BLINDING_CRITERIA_EXPRESSION](#).

Modify Column Display Characteristics in a Clinical Data Model Table

Use this API to update display characteristic attributes of columns.

Name

DME_PUB_DF_DATA_MODEL.ModifyColDispChars

Signature

```
procedure dme_pubdf_data_model.ModifyColDisPChars
(p_api_version                IN NUMBER
,p_init_msg_list              IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
,p_commit                     IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
,p_validation_level           IN NUMBER default
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
,x_return_status              OUT NOCOPY VARCHAR2
,x_msg_count                   OUT NOCOPY NUMBER
,x_msg_data                    OUT NOCOPY VARCHAR2
,piModTabDCColl               IN DME_MOD_DC_COLL
,pi_lifeCycleRc               in varchar2 default '$LIFECYCLE$DEV') ;
```

Parameters

This API has standard parameters (see [Standard Parameters](#)).

API Input Collections

This API takes a nested collection of model-table-columns.

DME_MOD_DC_COLL:

Table of **DME_MOD_DC_TYPE**

DME_MOD_DC_TYPE:

```
OBJECT
(
  COMPANY_ID                NUMBER(6),
  OBJ_ID                    NUMBER(22),
  OBJ_VER                   NUMBER(7),
  OBJECT_VERSION_NUMBER     NUMBER(9),
  NAMESPACE_OBJ_ID         NUMBER(22),
  NAMESPACE_OBJ_VER        NUMBER(7),
  OBJECT_SUBTYPE_ID         NUMBER(22),
  TABDISPCHARCOLL          DME_TAB_DC_COLL,
  constructor function DME_MOD_DC_TYPE return self as result
)
```

DME_TAB_DC_COLL:

Table Of **DME_TAB_DC_TYPE**

DME_TAB_DC_TYPE:

```
OBJECT
(
  COMPANY_ID                NUMBER(6),
  OBJ_ID                    NUMBER(22),
  OBJ_VER                   NUMBER(7),
  OBJECT_VERSION_NUMBER     NUMBER(9),
  NAMESPACE_OBJ_ID         NUMBER(22),
  NAMESPACE_OBJ_VER        NUMBER(7),
  MODIFY_DISPLAY_ORDER      VARCHAR2(10),
  colDispCharColl          DME_COL_DISP_CHARS_COLL,
  constructor function DME_TAB_DC_TYPE return self as result
)
```

DME_DISP_CHARS_COLL:

Table Of **DME_COL_DISP_CHARS_TYPE**

DME_COL_DISP_CHARS_TYPE:

```
OBJECT
(
  "COMPANY_ID"              NUMBER(6),
  "COL_OBJ_ID"              NUMBER(22),
  "LIFECYCLE_AREA_RC"       VARCHAR2(30),
  "DISPLAY_WIDTH"           NUMBER(22),
  "DISPLAY_HEADER"          VARCHAR2(4000),
  "DISPLAY_HOVER_TEXT"      VARCHAR2(4000),
  "DISPLAY_FLAG_RC"         VARCHAR2(30),
  "NOT_USED_FLAG_RC"        VARCHAR2(30),
  "DISPLAY_ORDER"           NUMBER(10),
```

```
"OBJECT_VERSION_NUMBER"    NUMBER(9),
constructor function DME_COL_DISP_CHARS_TYPE return self as result
)
```

Modify a Column in a Clinical Data Model Table

Use this API to modify a column.

Name

DME_PUB_DF_DATA_MODEL.ModifyColumnInDataModelTab

Signature

```
procedure ModifyColumnInDataModelTab(p_api_version      IN NUMBER
p_init_msg_list      IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
p_commit             IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
p_validation_level    IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
x_return_status       OUT NOCOPY VARCHAR2
x_msg_count          OUT NOCOPY NUMBER
x_msg_data           OUT NOCOPY VARCHAR2
pio_naming            IN OUT NOCOPY cdr_naming_version_obj_type
pio_column           IN OUT NOCOPY cdr_dm_column_obj_type );
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory): Enter values for the column. This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE.
- **PIO_COLUMN** (Mandatory): This is a parameter of type CDR_DM_COLUMN_OBJ_TYPE. Enter current or modified values for the column as required.

Remove Column from Clinical Data Model Table

Use this API to delete a column from a table.

Name

DME_PUB_DF_DATA_MODEL.RemoveColumnsInDataModelTab

Signature

```
procedure RemoveColumnsInDataModelTab(
p_api_version      IN NUMBER,
p_init_msg_list      IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE,
p_commit           IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE,
p_validation_level  IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
x_return_status     OUT NOCOPY VARCHAR2,
x_msg_count        OUT NOCOPY NUMBER,
x_msg_data         OUT NOCOPY VARCHAR2,
pi_naming_coll      IN  cdr_naming_list_coll);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PI_NAMING_COLL (Mandatory): Identify the column to be removed. This is a parameter of type CDR_NAMING_LIST_COLL.

Add a Constraint to a Clinical Data Model Table

Use this API to add a constraint to a table in a study or library clinical data model.

Name

DME_PUB_DF_DATA_MODEL.AddConstraintToDataModelTab

Signature

```
procedure AddConstraintToDataModelTab(
  p_api_version      IN NUMBER
  p_init_msg_list     IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  p_commit           IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  p_validation_level  IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
  x_return_status     OUT NOCOPY VARCHAR2
  x_msg_count        OUT NOCOPY NUMBER
  x_msg_data         OUT NOCOPY VARCHAR2
  pio_naming         IN OUT NOCOPY cdr_naming_version_obj_type
  pio_constraint      IN OUT NOCOPY cdr_dm_tab_cons_obj_type
  pi_constraintColumns IN OUT NOCOPY cdr_table_concols_list_coll
  pi_vals            IN cdr_vals_coll);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter values for the new constraint and the parent table. The following attributes are required:
 - **COMPANY_ID**: Company ID of the Data Model,
 - **OBJECT_TYPE_RC**: Enter '\$OBJTYPES\$TABLECNSTR'
 - **NAME**: Name of the constraint.
 - **NAMESPACE_OBJ_ID**: Object ID of the Data Model.
 - **NAMESPACE_OBJ_VER**: Object Version of the Data Model.
- **PIO_CONSTRAINT** (Mandatory): This is a parameter of type CDR_DM_TAB_CONS_OBJ_TYPE. Enter values as follows:
 - **COMPANY_ID**: To get your company ID, use CDR_PUB_DEF_FACTORY_UTILS.GetCompanyId.
 - **OBJ_ID** and **OBJ_VER**: Enter NULL.
 - **CONSTRAINT_NAME**: Enter a name.
 - **CONSTRAINT_TYPE_RC**: Identify the type of constraint:
 - \$CONSTRAINTTYPES\$CHECK
 - \$CONSTRAINTTYPES\$PRIMARYKEY
 - \$CONSTRAINTTYPES\$BITMAP
 - \$CONSTRAINTTYPES\$UNIQUE
 - \$CONSTRAINTTYPES\$NUINDEX
 - **SURROGATE_KEY_FLAG_RC**: Enter null. If you are creating a primary key and a surrogate key column does not exist in the table, the system creates it as CDR\$SKEY. The column stores surrogate key values, which are required for data lineage tracing.

- **DUPLICATE_RECORD_FLAG_RC**: The system uses this value only for primary keys. In most cases this should be set to '\$YESNO\$NO' but you can enable loading records with the same primary key value by entering '\$YESNO\$YES'. See the *Oracle Life Sciences Data Management Workbench User's Guide* for more information.
- **DM_CONS_COL_COLL**: Pass NULL values.
- **PI_CONSTRAINTCOLUMNS**: This is a parameter of type CDR_TABLE_CONCOLS_LIST_COLL. Identify the table and the table's columns where you want to apply the constraints. Depending on the constraint, you must also provide values for attributes that define foreign key, or that identify the list of values object to store the values for a CHECK constraint.
 - **TABC_COMPANY_ID**: To get your company ID, use CDR_PUB_DEF_FACTORY_UTILS.GetCompanyId.
 - **TABC_OBJ_ID** and **TABC_OBJ_VER**: Enter NULL.
 - FK_COL_COMPANY_ID**: Enter NULL.
 - FK_COL_OBJ_ID**: Enter NULL.
 - FK_COL_OBJ_VER**: Enter NULL.
 - POSITION**: Enter the position of the constraint column in constraint.
 - COL_COMPANY_ID**: Enter the column company ID.
 - COL_OBJ_ID**: Enter the column's object ID.
 - COL_OBJ_VER**: Enter the column's object version.
 - LOV_COMPANY_ID**: Enter the column company ID.
 - LOV_OBJ_ID**: Enter NULL.
 - LOV_OBJ_VER**: Enter NULL.
- **PI_VALS**. This is a parameter of type CDR_VALS_COLL that is based on CDR_VAL_OBJ_TYPE type. It applies only to Check constraints. The type has two attributes for each value.
 - **POSITION**: The position of the value in the list.
 - **VALUE**: The valid value.

Modify a Constraint in a Clinical Data Model Table

Use this API to modify an existing constraint.

Name

DME_PUB_DF_DATA_MODEL.ModifyConsInDataModelTab

Signature

```
procedure ModifyConsInDataModelTab(p_api_version      IN NUMBER
p_init_msg_list      IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
p_commit             IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
p_validation_level    IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
x_return_status       OUT NOCOPY VARCHAR2
x_msg_count           OUT NOCOPY NUMBER
x_msg_data            OUT NOCOPY VARCHAR2
pio_naming            IN OUT NOCOPY cdr_naming_version_obj_type
pio_constraint        IN OUT NOCOPY cdr_dm_tab_cons_obj_type)
```

```
pi_constraintColumns IN OUT NOCOPY cdr_table_concols_list_coll
pi_vals IN cdr_vals_coll );
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory): Enter values for the constraint. This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE.
- **PIO_CONSTRAINT**(Mandatory): This is a parameter of type CDR_DM_TAB_CONS_OBJ_TYPE. Enter current or modified values for the constraint as required.
- **PI_VALS**. This is a parameter of type CDR_VALS_COLL that is based on CDR_VAL_OBJ_TYPE type. Enter current or modified values for a check constraint as required.

Remove Constraint from a Clinical Data Model Table

Use this API to remove a constraint from a table.

Name

DME_PUB_DF_DATA_MODEL.RemoveConsInDataModelTab

Signature

```
procedure RemoveConsInDataModelTab(
  p_api_version      IN NUMBER
  p_init_msg_list     IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  p_commit           IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  p_validation_level  IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
  x_return_status     OUT NOCOPY VARCHAR2
  x_msg_count        OUT NOCOPY NUMBER
  x_msg_data         OUT NOCOPY VARCHAR2
  pi_naming_coll     IN  cdr_naming_list_coll);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PI_NAMING_COLL (Mandatory): Identify the constraint to be removed. This is a parameter of type CDR_NAMING_LIST_COLL that contains list of CDR naming version attributes.

Reorder Columns in a Clinical Data Model Table

Use this API to change the order of columns in a table.

Name

DME_PUB_DF_DATA_MODEL.ReorderColumnInDMTable

Signature

```
procedure ReorderColumnInDMTable(
  p_api_version      IN NUMBER
  p_init_msg_list     IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
  p_commit           in varchar2 default cdr_pub_def_constants.g_false
  p_validation_level  in number default cdr_pub_def_constants.g_valid_level_full
  pi_reorderObjColl IN  cdr_reorder_obj_coll
```

```
x_return_status    OUT NOCOPY VARCHAR2
x_msg_count        OUT NOCOPY NUMBER
x_msg_data         OUT NOCOPY VARCHAR2);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PI_REORDEROBJCOLL (Mandatory): This is a parameter of type CDR_REORDER_OBJ_COLL, which is based on the CDR_REORDER_OBJ_TYPE type. Pass one set of CDR_REORDER_OBJ_TYPE to CDR_REORDER_OBJ_COLL for each column whose order needs to be changed.

- **COMPANY_ID**: To get your company ID, use CDR_PUB_DEF_FACTORY_UTILS.GetCompanyId.
- **OBJ_ID**: Enter the column's object ID.
- **OBJ_VER**: Enter the column's object version.
- **NAMESPACE_OBJ_ID**: Enter the table's object ID.
- **NAMESPACE_OBJ_VER**: Enter the table's object version.
- **POSITION**: Enter the new position for the column, relative to other columns in the table.
- **ENTRY_NUMBER**: Enter null.
- **OBJECT_VERSION_NUMBER**: Enter null.

Display Metadata Differences between Tables

Use this API to display the differences found when comparing metadata in two tables.

Name

DME_PUB_DF_DATA_MODEL.get_tab_metadata_diff

Signature

```
FUNCTION GET_TAB_METADATA_DIFF
(piCompID          IN CDR_NAMINGS.COMPANY_ID%TYPE
,piSrcTabObjID    IN CDR_NAMINGS.OBJ_ID%TYPE
,piSrcTabObjVer    IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE
,piTgtTabObjID    IN CDR_NAMINGS.OBJ_ID%TYPE
,piTgtTabObjVer    IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE
) RETURN dme_char_coll;
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **COMPANY_ID** (Mandatory): To get your company ID, use CDR_PUB_DEF_FACTORY_UTILS.GetCompanyId.
- **TABLE1_OBJID** (Mandatory): The object ID of the first table being compared.
- **TABLE1_OBJVER** (Mandatory): The object version of the first table being compared.
- **TABLE2_OBJID** (Mandatory): The object ID of the second table being compared.
- **TABLE2_OBJVER** (Mandatory): The object version of the second table being compared.

Validate the Derived Encoding Date Through TMS

API to validate the TMS Encoding Date.

Use this API to validate the TMS Encoding Date. This public API returns the reencoding date for an Oracle DMW term classified through TMS successfully for scenarios where TMS term is reclassified on the TMS-side directly. The subsequent data load in Oracle DMW reclassifies the term during TMS post-processing.

Name

DME_PUB_XFORM_MAP.getTMSReEncodingDate

Signature

```
function dme_pub_xform_map.getTMSReEncodingDate (  
    p_api_version IN VARCHAR2,  
    p_init_msg_list IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,  
    p_commit IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE,  
    p_validation_level IN NUMBER default  
    CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
    x_return_status OUT NOCOPY VARCHAR2,  
    x_msg_count OUT NOCOPY NUMBER,  
    x_msg_data OUT NOCOPY VARCHAR2,  
    p_sourceTermId IN NUMBER  
)
```

return date: It returns the reencoding date for the p_sourceTermId that is passed. The API looks up the reencoding date in an internal TMS table for the given p_sourceTermId. If p_sourceTermId is passed as null, the API returns the reencoding date as null.

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **p_api_version** (Mandatory): Enter the current version of the API you are calling. The API compares the version numbers of incoming calls to its current version number and returns an error if they are incompatible.
- **p_init_msg_list** (Optional): Accept the default value (FND_API.G_FALSE) to ensure that this individual API does not initialize the message list upon completion. Pass FND_API.G_TRUE to override the default behavior.
- **p_commit** (Optional): Accept the default value (FND_API.G_FALSE) to ensure that this individual API does not commit upon completion. Pass FND_API.G_TRUE to override the default behavior.
- **p_validation_level** (Optional): Accept the default value to perform full validation. No other values are currently supported.
- **x_return_status**: This output parameter returns the end status of the API: (S) Success, (E) Error, or (U) Unexpected Error
- **x_msg_count**: This output parameter returns the count of error messages if the return status is other than Success.
- **x_msg_data**: This output parameter returns the text of the error message, if the message count is 1. If there are more than one messages, use cdr_pub_msg_pub.get to retrieve the messages.

- **p_sourceTermId** (Mandatory): Enter the TERM_ID of the source term stored in DMW.

Get a Custom Listing Business Area ID for a Model

When a user logs into a visualization tool, the visualization tool must call an API to initialize the primary data model schema and, if the user wants to see custom listings through the tool, the schema for custom listings. The initialization API requires the business area instance ID, which is not available to a user in DMW.

Use this API to fetch the ID of the business area instance that contains all the custom listings defined in the model.

Name

CDR_PUB_API_GVA.getCustomListingBA

Signature

```
FUNCTION getCustomListingBA(  
pi_nDataModelId IN NUMBER,  
pi_vContext IN VARCHAR2)  
RETURN NUMBER;
```

Parameters

pi_nDataModelId Enter the ID of the data model.

pi_vContext Enter the life cycle context value. The allowed values are: \$LIFECYCLE\$DEV, \$LIFECYCLE\$PROD, or \$LIFECYCLE\$QC.

See the following topic for details:

- [Required Profile for Custom Listing BAs](#)

Required Profile for Custom Listing BAs

You must set profile DMW : Synch Custom Listing BA synonyms with Primary Datamodel Business Area to Yes to generate custom listing business areas.

- If set to **No**, custom listing business area synonyms are not added to the primary business area for the model. This is the default value.
- If set to **Yes**, and if the data model is set to allow business areas, during installation of either the model or any custom listing that reads from it, the system creates synonyms in the primary schema based on custom listing names.

Codelists

This is a public interface for all operations related to codelists, including creation, deletion, modification, and checking in and out of these objects.

This section contains the following topic:

- [Create and Modify Codelists](#)

Create and Modify Codelists

This section contains the following public APIs in package DME_PUB_CODE_LISTS:

- [Create a Codelist](#)
- [Modify a Codelist](#)
- [Remove a Codelist](#)
- [Check In a Codelist](#)
- [Check Out a Codelist](#)
- [Add Values to a Codelist](#)
- [Remove Values from a Codelist](#)
- [Get Codelist Details for a Given Column](#)

Create a Codelist

Use this API to create a codelist under a library domain. Codelists created with this API can be verified through public view 'DME_PUB_CODELIST_V'. For values refer 'DME_PUB_CODELIST_VALUES_V'.

Name

DME_PUB_CODE_LISTS.CreateCodeList

Signature

```
PROCEDURE CREATECODELIST
(P_API_VERSION      IN NUMBER,
P_INIT_MSG_LIST     IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT            IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL  IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
P_NAMING             IN OUT NOCOPY cdr_naming_version_obj_type,
P_CODELISTCOLL      IN CDR_CODE_LIST_COLL,
X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER,
X_MSG_DATA OUT NOCOPY VARCHAR2,
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) as well as the following parameters:

- **P_NAMING** (Mandatory). This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. For OBJECT_TYPE_RC enter '\$OBJTYPES\$CODELIST'.
- **P_CODELISTCOLL** (Optional). This is a parameter of type CDR_CODE_LIST_COLL. Collection of code value pairs. For example:

```
CDR_CODE_LIST_COLL(CDR_CODE_LIST_OBJ_TYPE('CDE1', 'VAL1'),
CDR_CODE_LIST_OBJ_TYPE('CDE2', 'VAL2');
```

Modify a Codelist

Use this API to modify the name and description of a codelist. Codelists modified with this API can be verified through public view 'DME_PUB_CODELIST_V'.



Note:

To add code-value pairs, see [Add Values to a Codelist](#).

Name

DME_PUB_CODE_LISTS.ModifyCodeList

Signature

```
PROCEDURE MODIFYCODELIST
(P_API_VERSION      IN NUMBER,
P_INIT_MSG_LIST     IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT            IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL  IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
P_NAMING             IN OUT NOCOPY CDR_NAMING_VERSION_OBJ_TYPE,
X_RETURN_STATUS     OUT NOCOPY VARCHAR2,
X_MSG_COUNT         OUT NOCOPY NUMBER,
X_MSG_DATA          OUT NOCOPY VARCHAR2,
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) as well as the following parameter:

- **P_NAMING** (Mandatory). This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter values for the codelist whose code-value pairs you are modifying and the new attribute values, such as Name and Description. To get naming version attribute values see [Get a Naming Version Object](#).

Remove a Codelist

Use this API to remove a codelist. After this API is executed, public view 'DME_PUB_CODELIST_V' will not display the codelist.

Name

DME_PUB_CODE_LISTS.RemoveCodeList

Signature

```
PROCEDURE REMOVECODELIST
  (P_API_VERSION      IN NUMBER ,      P_INIT_MSG_LIST      IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE,      P_COMMIT              IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE,      P_VALIDATION_LEVEL IN NUMBER DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,      P_NAMING              IN OUT NOCOPY
  cdr_naming_version_obj_type,      X_RETURN_STATUS OUT NOCOPY VARCHAR2,      X_MSG_COUNT OUT
  NOCOPY      NUMBER,      X_MSG_DATA OUT NOCOPY      VARCHAR2
  );
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) as well as the following parameters:

- **P_NAMING** (Mandatory). This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter values for the codelist from which the code-value pairs have to be removed.

Check In a Codelist

Use this API to check in a codelist. Changed status can be verified through public view 'DME_PUB_CODELIST_V'.

Name

DME_PUB_CODE_LISTS.CheckinCodeList

Signature

```
PROCEDURE CHECKINCODELIST
  (P_API_VERSION      IN NUMBER,      P_INIT_MSG_LIST      IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE,      p_commit              IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE,      p_validation_level IN NUMBER DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,      p_naming              IN OUT NOCOPY
  cdr_naming_version_obj_type,      x_return_status OUT NOCOPY VARCHAR2,      x_msg_count OUT
  NOCOPY      NUMBER,      x_msg_data OUT NOCOPY      VARCHAR2
  );
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) as well as the following parameter:

- **P_NAMING** (Mandatory). This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter values for the codelist you are checking in.

Check Out a Codelist

Use this API to check out a codelist. Changed status can be verified through public view 'DME_PUB_CODELIST_V'.

Name

DME_PUB_CODE_LISTS.CheckoutCodeList

Signature

```
PROCEDURE CHECKOUTCODELIST
  ( P_API_VERSION      IN NUMBER ,      P_INIT_MSG_LIST      IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE,      P_COMMIT                IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE,      P_VALIDATION_LEVEL IN NUMBER DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,      P_NAMING                IN OUT NOCOPY
  cdr_naming_version_obj_type,      X_RETURN_STATUS OUT NOCOPY VARCHAR2,      X_MSG_COUNT OUT
  NOCOPY      NUMBER,      X_MSG_DATA OUT NOCOPY      VARCHAR2)
;
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) as well as the following parameter:

P_NAMING (Mandatory). This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter values for the codelist you are checking out.

Add Values to a Codelist

Use this API to add code value pairs to a codelist. Codelist values created with this API can be verified through public view 'DME_PUB_CODELIST_VALUES_V'.

**Note:**

You can add new code-value pairs but you cannot modify existing ones using this API. You can do that in the user interface, or you can remove existing pairs (see [Remove a Codelist](#)) and add new ones using APIs.

Name

DME_PUB_CODE_LISTS.AddCodeListValues

Signature

```
PROCEDURE ADDCODELISTVALUES
  (P_API_VERSION      IN NUMBER ,      P_INIT_MSG_LIST      IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE,      P_COMMIT                IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE,      P_VALIDATION_LEVEL IN NUMBER DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,      P_NAMING                IN OUT NOCOPY
  cdr_naming_version_obj_type ,      P_CODELISTCOLL      IN CDR_CODE_LIST_COLL ,
  X_RETURN_STATUS OUT NOCOPY VARCHAR2 ,      X_MSG_COUNT OUT NOCOPY      NUMBER ,
  X_MSG_DATA OUT NOCOPY      VARCHAR2)
;
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) as well as the following parameters:

- **P_NAMING** (Mandatory). This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Enter values for the codelist to which you are added code-value pairs.
- **P_CODELISTCOLL** (Mandatory). This is a parameter of type CDR_CODE_LIST_COLL. Collection of code value pairs. For example:

```
CDR_CODE_LIST_COLL(CDR_CODE_LIST_OBJ_TYPE('CDE1', 'VAL1'),
CDR_CODE_LIST_OBJ_TYPE('CDE2', 'VAL2'));
```

Remove Values from a Codelist

Use this API to remove code value pairs to a codelist. After this API is executed, public view 'DME_PUB_CODELIST_V' will not display the codelist values.

Name

DME_PUB_CODE_LISTS.AddCodeListValues

Signature

```
PROCEDURE REMOVECODELISTVALUES
(
  P_API_VERSION      IN NUMBER,
  P_INIT_MSG_LIST    IN VARCHAR2 DEFAULT
    CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT            IN VARCHAR2 DEFAULT
    CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_VALIDATION_LEVEL IN NUMBER DEFAULT
    CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  P_NAMING            IN OUT NOCOPY
    cdr_naming_version_obj_type,
  P_CODELISTCOLL      IN CDR_CODE_LIST_COLL,
  X_RETURN_STATUS OUT NOCOPY VARCHAR2,
  X_MSG_COUNT OUT NOCOPY NUMBER,
  X_MSG_DATA OUT NOCOPY VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) as well as the following parameters:

- **P_NAMING** (Mandatory). This is a parameter of type CDR_NAMING_VERSION_OBJ_TYPE. Whole naming object needs to be populated for the object which needs code values to be added to it. API 'CDR_PUB_DEF_FACTORY_SUPPORT.GETNAMINGOBJECT' can be used to populate naming object.
- **P_CODELISTCOLL** (Mandatory). This is a parameter of type CDR_CODE_LIST_COLL. Collection of code value pairs. For example:

```
CDR_CODE_LIST_COLL(CDR_CODE_LIST_OBJ_TYPE('CDE1', 'VAL1'),
CDR_CODE_LIST_OBJ_TYPE('CDE2', 'VAL2'));
```

Get Codelist Details for a Given Column

Use this API to get the codelist details for a given column.

Name

DME_PUB_CODE_LISTS.getCodeListDetail

Signature

```
PROCEDURE GETCODELISTDETAIL
(
  P_API_VERSION      IN NUMBER ,
  P_INIT_MSG_LIST    IN VARCHAR2 DEFAULT
    CDR_PUB_DEF_CONSTANTS.G_FALSE,
  P_COMMIT            IN VARCHAR2 DEFAULT
```

```
CDR_PUB_DEF_CONSTANTS.G_FALSE,      P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,    X_RETURN_STATUS OUT NOCOPY VARCHAR2 ,
X_MSG_COUNT OUT NOCOPY      NUMBER,    X_MSG_DATA OUT NOCOPY      VARCHAR2,
PI_COLCOMPANYID      IN cdr_naming_versions.company_id%type,    PI_COLOBJID      IN
cdr_naming_versions.obj_id%type,    PI_COLOBJVER      IN
cdr_naming_versions.obj_ver%type,    PO_CODELISTID      OUT NOCOPY
cdr_naming_versions.obj_id%type,    PO_CODELISTVER      OUT NOCOPY
cdr_naming_versions.obj_Ver%type
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) as well as the following parameters:

- **PI_COLCOMPANYID** (Mandatory). COMPANY_ID of a Column.
- **PI_COLOBJID** (Mandatory). Object Identifier of a Column
- **PI_COLOBJVER** (Mandatory). Object Version of a Column
- **PO_CODELISTID** This is out parameter. It returns the Object Id of associated codelist.
- **PO_CODELISTVER** This is out parameter. It returns the Object Version of associated codelist.

Flags, Categories, and Actions

This is a public interface for operations related to flags and actions. It contains the following topics:

- [Flag-Related APIs](#)
- [Flag Name-Related APIs](#)
- [Get Flag States](#)
- [Clinical Data Model Category-Related APIs](#)
- [Action-Related APIs](#)

Flag-Related APIs

This section contains the following procedures related to flags in the package DME_PUB_FLAG_DATA.

**Note:**

A program that calls any of these flag APIs must call DME_PUB_INITIALIZATION.SetupAPIStudyEnvironment to set the study and lifecycle context after calling CDR_PUB_API_INITIALIZATION.enableAPIs.

- [Set Flag](#)
- [Get Flag](#)
- [Get Flags on Data](#)
- [Get Flags on Data Fuller](#)
- [Delete Flag](#)
- [Get Surrogate Key Values for Records in a Flag State](#)

Set Flag

Use this API to set the state of a single flag for a given record.

Name

DME_PUB_FLAG_DATA.SetFlag

Signature

```
PROCEDURE SETFLAG,  
( P_API_VERSION IN VARCHAR2,  
  P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,  
  P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
```

```

X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER,
X_MSG_DATA OUT NOCOPY VARCHAR2,
PI_COMPANY_ID IN NUMBER,
PI_TAB_OBJ_ID IN NUMBER,
PI_SKEY_VALUE IN VARCHAR2,
PI_TIMESTAMP IN DATE,
PI_FLAG_ID IN NUMBER,
PI_FLAG_STATE IN VARCHAR2,
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPANY_ID** (Mandatory). Enter the company ID.
- **PI_TAB_OBJ_ID** (Mandatory). Enter the object ID of the table instance that contains the data record.
- **PI_SKEY_VALUE** (Mandatory). Enter the surrogate key of the record.
- **PI_TIMESTAMP** Enter the latest timestamp of the data record. The system tracks which version of the record the flag was initially applied to.
- **PI_FLAG_ID** (Mandatory). Enter the unique ID of the flag (from dme_flag_names)
- **PI_FLAG_STATE** (Mandatory). The flag state to be applied for the data record.

Get Flag

Use this API to retrieve information about an Oracle DMW flag setting.

Name

DME_PUB_FLAG_DATA.GetFlag

Signature

```

PROCEDURE GETFLAG
( P_API_VERSION IN VARCHAR2,
P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER,
X_MSG_DATA OUT NOCOPY VARCHAR2,
PI_COMPANY_ID IN NUMBER,
PI_TAB_OBJ_ID IN NUMBER,
PI_SKEY_VALUE IN VARCHAR2,
PI_FLAG_ID IN NUMBER,
PO_FLAG_STATE OUT NOCOPY VARCHAR2,
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPANY_ID** (Mandatory). Enter the company ID.
- **PI_TAB_OBJ_ID** (Mandatory). Enter the obj_id of the table instance that contains the data record.
- **PI_SKEY_VALUE** (Mandatory). The surrogate key of the record

- **PI_FLAG_ID** (Mandatory). The unique ID of the flag (from dme_flag_names)
- **PO_FLAG_STATE** (Mandatory). This output parameter inherits the flag state for this record.

Get Flags on Data

This API retrieves all the flags and their states, assigned to a particular data record, plus the latest update timestamp for each flag category per record.

It does not provide a timestamp for each individual flag update. If you want to see the update timestamp for a particular flag, you can create a category for that one flag.

Name

DME_PUB_FLAG_DATA.GetFlagsOnDataMore

Signature

```
PROCEDURE getFlagsOnDataMore
(
  p_api_version IN VARCHAR2
, p_init_msg_list IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE
, p_commit IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
, p_validation_level IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
, x_return_status OUT NOCOPY VARCHAR2
, x_msg_count OUT NOCOPY NUMBER
, x_msg_data OUT NOCOPY VARCHAR2
, pi_company_id IN NUMBER
, pi_tab_obj_id IN NUMBER
, pi_skey_value IN VARCHAR2
, pi_include_nulls IN NUMBER
, po_flags OUT NOCOPY dme_flag_show_more_coll
) ;
```

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPANY_ID** (Mandatory). Enter the company ID.
- **PI_TAB_OBJ_ID** (Mandatory). This input parameter is an object ID for a namings object of type \$OBJTYPES\$TABLEREF (table instance).
- **PI_SKEY_VALUE** (Mandatory). Enter the surrogate key of the record whose flags you want to retrieve.
- **PI_INCLUDE_NULLS** (Mandatory). Set this input parameter to 1 to include information for flags with NULL state, else 0.
- **PO_FLAGS** (Output). This is a parameter of type DME_FLAG_SHOW_MORE_COLL that returns:
 - Flag ID
 - Flag Name
 - Flag Value
 - Flag State Priority Code
 - Flag State Priority Meaning
 - Category ID
 - Most Recent Category Update Date (The most recent update of any flag in the category.)

- Category Update User ID (The user ID of the user or validation check that performed the most recent flag assignment update in the category.)
- Category Update Username (The name of the user or validation check that performed the most recent flag assignment update in the category.)

Get Flags on Data Fuller

This API retrieves information about all the flag states on a particular record.

Name

DME_PUB_FLAG_DATA.GetFlagsOnDataFuller

Signature

```
PROCEDURE getFlagsOnDataFuller
(
  p_api_version IN VARCHAR2
, p_init_msg_list IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE
, p_commit IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
, p_validation_level IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
, x_return_status OUT NOCOPY VARCHAR2
, x_msg_count OUT NOCOPY NUMBER
, x_msg_data OUT NOCOPY VARCHAR2
, pi_company_id IN NUMBER
, pi_tab_obj_id IN NUMBER
, pi_skey_value IN VARCHAR2
, po_flags OUT NOCOPY dme_flag_show_ver4_coll
);
```

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPANY_ID** (Mandatory). Enter the company ID.
- **PI_TAB_OBJ_ID** (Mandatory). This input parameter is an object ID for a namings object of type \$OBJTYPES\$TABLEREF (table instance).
- **PI_SKEY_VALUE** (Mandatory). Enter the surrogate key of the record whose flags you want to retrieve.
- **PO_FLAGS** (Mandatory). This is a parameter of type DME_FLAG_SHOW_VER4_COLL that returns: or the returned values (names, states, priorities, last category update date and last category update user)
 - Flag Name
 - Flag State Priority Code
 - Flag State Priority Meaning
 - Most Recent Category Update Date (The most recent update of any flag in the category.)
 - Category Update Username (The name of the user or validation check that performed the most recent flag assignment update in the category.)

Delete Flag

Use this API to delete an existing DMW Flag state.

Name

DME_PUB_FLAG_DATA.DeleteFlag

Signature

```
PROCEDURE DELETEFLAG
(P_API_VERSION IN VARCHAR2,
P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER,
X_MSG_DATA OUT NOCOPY VARCHAR2,
PI_COMPANY_ID IN NUMBER,
PI_TAB_OBJ_ID IN NUMBER,
PI_SKEY_VALUE IN VARCHAR2,
PI_FLAG_ID IN NUMBER,
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPANY_ID** (Mandatory). Enter the company ID.
- **PI_TAB_OBJ_ID** (Mandatory). This input parameter is an object id for a namings object of type \$OBJTYPES\$TABLEREF (table instance).
- **PI_SKEY_VALUE** (Mandatory). The surrogate key of the record.
- **PI_FLAG_ID** (Mandatory). This input parameter is the ID of the flag whose state you want to remove.

Get Surrogate Key Values for Records in a Flag State

Use this API to get the surrogate keys for all records in a table that have the given state for the given flag.

Name

DME_PUB_FLAG_DATA.getRecordsForFlagState

Signature

```
PROCEDURE getRecordsForFlagState
( p_api_version IN VARCHAR2
, p_init_msg_list IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE
, p_commit IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
, p_validation_level IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
, x_return_status OUT NOCOPY VARCHAR2
, x_msg_count OUT NOCOPY NUMBER
, x_msg_data OUT NOCOPY VARCHAR2
, pi_company_id IN NUMBER
, pi_tab_obj_id IN NUMBER
, pi_flag_id IN NUMBER
, pi_flag_state IN VARCHAR2
, pi_records OUT NOCOPY dme_char_coll);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPANY_ID** (Mandatory). Enter the company ID.
- **PI_TAB_OBJ_ID** (Mandatory). Enter the object id for a namings object of type \$OBJTYPES\$TABLEREF (table instance) that contains the record.
- **PI_FLAG_ID** (Mandatory). Enter the ID of the flag.
- **PI_FLAG_STATE** (Mandatory). Enter the flag state.
- **PI_RECORDS** This output parameter is a collection of type dme_char_coll.

Flag Name-Related APIs

Use the following APIs in the package DME_PUB_FLAG_NAME to retrieve DMW flag names definitions and states. Use the first version of these APIs if you know the flag ID; use the second one if you know its name.



Note:

A program that calls any of these flag APIs must call DME_PUB_INITIALIZATION.SetupAPIStudyEnvironment to set the study and lifecycle context after calling CDR_PUB_API_INITIALIZATION.enableAPIs.

This section includes the following:

- [Get Flag Name Definition, Version 1](#)
- [Get Flag Name Definition, Version 2](#)
- [Get Flag Name Definitions](#)

Get Flag Name Definition, Version 1

Use this API to retrieve information about an Oracle DMW flag name definition. Use this API if you know the Flag Name ID.

Name

DME_PUB_FLAG_NAME.GetFlagName

Signature

```
PROCEDURE GETFLAGNAME
(P_API_VERSION IN VARCHAR2,
P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER,
X_MSG_DATA OUT NOCOPY VARCHAR2,
PI_COMPANY_ID IN NUMBER,
PI_FLAG_NAME_ID IN NUMBER,
PIO_DME_FLAG_NAME IN OUT NOCOPY DME_FLAG_NAME_TYPE,
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPANY_ID** (Mandatory). Enter the company ID.
- **PI_FLAG_NAME_ID** (Mandatory). Enter the ID of the flag name definition to be retrieved.
- **PIO_DME_FLAG_NAME** (Mandatory). This is a parameter of type DME_FLAG_DEF_NAME for the returned values.

Get Flag Name Definition, Version 2

Use this API to retrieve information about an Oracle DMW flag name definition. Use this API if you know the flag name.

Name

DME_PUB_FLAG_NAME.GetFlagName

Signature

```
PROCEDURE GETFLAGNAME
(P_API_VERSION IN VARCHAR2,
P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER,
X_MSG_DATA OUT NOCOPY VARCHAR2,
PI_COMPANY_ID IN NUMBER,
PI_FLAG_NAMESTR IN VARCHAR2,
PIO_DME_FLAG_NAME IN OUT NOCOPY DME_FLAG_NAME_TYPE,
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPANY_ID** (Mandatory). Enter the company ID.
- **PI_FLAG_NAMESTR** (Mandatory). Enter the name of the flag name definition to be retrieved.
- **PIO_DME_FLAG_NAME** (Mandatory). This is a parameter of type DME_FLAG_DEF_NAME for the returned values.

Get Flag Name Definitions

Use this API to retrieve information about DMW flag name definitions.

Name

DME_PUB_FLAG_NAME.GetFlagNames

Signature

```
PROCEDURE GETFLAGNAMES
( P_API_VERSION IN VARCHAR2,
P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER,
X_MSG_DATA OUT NOCOPY VARCHAR2,
```

```

PI_CATEGORY_ID IN NUMBER DEFAULT NULL,
PI_SUBJECT_VISIT IN VARCHAR2 DEFAULT NULL,
PI_USER_SETTABLE IN VARCHAR2 DEFAULT NULL,
PO_FLAG_NAMES OUT NOCOPY DME_FLAG_NAME_COLL,
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_CATEGORY_ID** (Optional). Set to null to retrieve flags in all categories. To get flags from a given category, provide a valid category ID.
- **PI_SUBJECT_VISIT** (Optional). Set to null to retrieve all flags irrespective of their being marked as subject_visit flags or not. To retrieve only subject_visit flags, enter either \$YESNO\$YES. To retrieve only record flags, enter \$YESNO\$NO.
- **PI_USER_SETTABLE** (Optional). Set to null to retrieve flags whether or not they are settable by the user. To retrieve only user-settable flags, enter \$YESNO\$YES. To retrieve flags not settable by users, enter \$YESNO\$NO.
- **PO_FLAG_NAMES** (Mandatory). This is a parameter of type DME_FLAG_NAME_COLL for the returned values.

Get Flag States

Use this API to retrieve information about all the DMW flag states for a single flag.

Name

DME_PUB_FLAG_STATE.GetFlagStates

Signature

```

PROCEDURE GETFLAGSTATES
(P_API_VERSION IN VARCHAR2,
P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER,
X_MSG_DATA OUT NOCOPY VARCHAR2,
PI_COMPANY_ID IN NUMBER,
PI_FLAG_NAME_ID IN NUMBER,
PO_DME_FLAG_STATES OUT NOCOPY DME_FLAG_STATE_COLL,
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPANY_ID** (Mandatory). Enter the company ID.
- **PI_FLAG_NAME_ID** (Mandatory). Enter the ID of the flag.
- **PO_DME_FLAG_STATES** (Mandatory). This is a parameter of type DME_FLAG_STATE_COLL for the returned information.

Clinical Data Model Category-Related APIs

This section includes the following:

**Note:**

You can create categories in the Oracle DMW Administration user interface.

- [Create Model Flag Category Mapping](#)
- [Get Categories for Model](#)

Create Model Flag Category Mapping

Use this API to create a map between a model type and subtype and a flag category.

Name

DME_PUB_MODEL_FLAGCAT.CreateModelFlagcatMap

Signature

```
PROCEDURE CREATEMODELFLAGCATMAP,
(P_API_VERSION IN VARCHAR2,
P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER,
X_MSG_DATA OUT NOCOPY VARCHAR2,
PI_COMPANY_ID IN NUMBER,
PI_MODEL_TYPE_RC IN VARCHAR2,
PI_MODEL_SUBTYPE_RC IN VARCHAR2,
PI_CATEGORY_ID IN NUMBER,
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPANY_ID** (Mandatory). Enter the company ID.
- **PI_MODEL_TYPE_RC** (Mandatory). Enter a model type from the lookup CDR_MODELTYPES such as \$MODELTYPE\$INPUT.
If you want to map a flag category to input models that come from files, pass these two arguments as '\$MODELTYPE\$INPUT' and '\$INPUTMODTYPE\$FILE'.
If you want to map a flag category to input models from InForm, pass these two arguments as '\$MODELTYPE\$INPUT' and '\$INPUTMODTYPE\$INFORM'.
If you want to map a flag category to target models, pass these arguments as '\$MODELTYPE\$TARGET' and NULL.
- **PI_MODEL_SUBTYPE_RC** (Mandatory). Enter a model subtype; for example, \$MODELTYPE\$INPUT or \$MODELTYPE\$TARGET
- **PI_CATEGORY_ID** (Mandatory). Enter the unique ID of the category (from dme_categories in the Administration Area of the DMW User Interface).

Get Categories for Model

Use this API to get all categories that are valid for a model type and subtype.

Name**DME_PUB_MODEL_FLAGCAT.GetCategoriesForModel****Signature**

```
PROCEDURE GETCATEGORIESFORMODEL,  
P_API_VERSION IN VARCHAR2,  
P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,  
P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,  
P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,  
X_RETURN_STATUS OUT NOCOPY VARCHAR2,  
X_MSG_COUNT OUT NOCOPY NUMBER,  
X_MSG_DATA OUT NOCOPY VARCHAR2,  
PI_COMPANY_ID IN NUMBER,  
PI_MODEL_TYPE_RC IN VARCHAR2,  
PI_MODEL_SUBTYPE_RC IN VARCHAR2,  
PO_CATEGORIES OUT NOCOPY DME_NUMBER_COLL,  
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_COMPANY_ID** (Mandatory). Enter the company ID.
- **PI_MODEL_TYPE_RC** (Mandatory). Enter a model type such as \$MODELTYPE\$INPUT, from the lookup CDR_MODELTYPES.
- **PI_MODEL_SUBTYPE_RC** (Mandatory). Enter a model subtype; for example, \$INPUTMODTYPE\$FILE.
- **PO_CATEGORIES** Output parameter returns an array of category IDs.

Action-Related APIs

Use the following APIs to perform tasks related to discrepancy actions:

- [Create Discrepancy Action](#)
- [Get Discrepancy Action, Version 1](#)
- [Get Discrepancy Action, Version 2](#)
- [Update Discrepancy Action](#)
- [Delete Discrepancy Action](#)

Create Discrepancy Action

Use this API to create a new discrepancy action.

Name**DME_PUB_DISC_ACTION.CreateDiscAction****Signature**

```
PROCEDURE CREATEDISCACTION (P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2  
DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT  
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT  
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
```

```
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PIO_DME_DISC_ACTION
IN OUT NOCOPY DME_DISC_ACTION_TYPE,) ;
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_DME_DISC_ACTION (Mandatory). This is a parameter of type DME_DISC_ACTION_TYPE that contains action attributes.

Enter the Start State, one of Candidate, Open, Answered, Cancelled, Closed. (In the API those are specified

as \$DISC_STATES\$CANDIDATE, \$DISC_STATES\$OPEN, \$DISC_STATES\$ANSWERED, \$DISC_STATES\$CANCELLED, and \$DISC_STATES\$CLOSED).

Get Discrepancy Action, Version 1

Use this API to retrieve information about an Oracle DMW Discrepancy Action.

Name

DME_PUB_DISC_ACTION.GetDiscAction

Signature

```
PROCEDURE GETDISCACTION( P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PI_ACTION_ID IN
NUMBER, PIO_DME_DISC_ACTION IN OUT NOCOPY DME_DISC_ACTION_TYPE, );
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_ACTION_ID** (Mandatory). Enter the ID of the discrepancy action to retrieve information for it.
- **PIO_DME_DISC_ACTION** (Mandatory). This is a parameter of type DME_DISC_ACTION_TYPE for the returned values.

Get Discrepancy Action, Version 2

Use this API to retrieve information about an Oracle DMW Discrepancy Action.

Name

DME_PUB_DISC_ACTION.GetDiscAction

Signature

```
PROCEDURE GETDISCACTION,
( P_API_VERSION IN VARCHAR2,
P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER,
X_MSG_DATA OUT NOCOPY VARCHAR2,
PI_ACTION_NAME IN VARCHAR2,
```

```
PIO_DME_DISC_ACTION IN OUT NOCOPY DME_DISC_ACTION_TYPE,
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_ACTION_NAME** (Mandatory). Provide the name of the discrepancy action to retrieve information for it.
- **PIO_DME_DISC_ACTION** (Mandatory). This is a parameter of type DME_DISC_ACTION_TYPE for the returned values.

Update Discrepancy Action

Use this API to modify an existing DMW Discrepancy Action.

Name

DME_PUB_DISC_ACTION.UpdateDiscAction

Signature

```
PROCEDURE UPDATEDISCACTION,
( P_API_VERSION IN VARCHAR2,
P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER,
X_MSG_DATA OUT NOCOPY VARCHAR2,
PIO_DME_DISC_ACTION IN OUT NOCOPY DME_DISC_ACTION_TYPE,
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

- **PIO_DME_DISC_ACTION** (Mandatory). This is a parameter of type DME_DISC_ACTION_TYPE that contains the discrepancy action attributes to be updated.

Delete Discrepancy Action

Use this API to delete an existing DMW Discrepancy Action.

Name

DME_PUB_DISC_ACTION.DeleteDiscAction

Signature

```
PROCEDURE DELETEDISCACTION,
(P_API_VERSION IN VARCHAR2,
P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER,
X_MSG_DATA OUT NOCOPY VARCHAR2,
PI_DME_DISC_ACTION_ID IN NUMBER,
);
```

Parameters:

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_DME_DISC_ACTION_ID** (Mandatory). This is a parameter of type NUMBER, that contains the unique ID of the category to be disabled.

Transformations

This is a public interface for all operations related to Transformation Maps, including creation, deletion, modification, and checking in and out of these objects.

See [Refresh Static Packages](#) for information about the package you must run whenever you add, change, or delete a custom program to be used in validation checks.

This chapter contains the following section:

- [Create and Modify Transformation Maps](#)

Create and Modify Transformation Maps

This section contains the following public APIs:

- [Create Transformation Maps](#)
- [Modify Transformation Maps](#)
- [Mark Table Maps Not Used](#)
- [Mark Column Maps Not Used](#)
- [Check In Transformation Maps](#)
- [Check Out Transformation Maps](#)
- [Undo Checkout Transformation Map](#)
- [Auto Map Tables](#)
- [Accept Table Mappings](#)
- [Auto Map Columns](#)
- [Get MappedTo Target Columns](#)
- [Accept Column Mappings](#)
- [Upgrade Transformation Map](#)
- [Install Transformation Map](#)
- [Remove Transformation Map](#)
- [Validate Transformation Maps](#)
- [Update Validation Status](#)
- [Execute Transformation Map](#)
- [Validate Expression](#)
- [Refresh Static Packages](#)

Create Transformation Maps

Use this API to create model-, table- and column-level transformation maps. Run this API multiple times to create the model-level mapping first, then each table mapping, and then each column mapping.

Name

DME_PUB_XFORM_MAP.CreateTransformationMap

Signature

```
PROCEDURE CREATETRANSFORMATIONMAP,
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PIO_XFORMMAP IN OUT
NOCOPY DME_XFORM_MAP_EX_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_XFORMMAP** (Mandatory). This is a parameter of DME_XFORM_MAP_EX_OBJ_TYPE object type. The attributes required for this API are:
 - **NAMING** This is an attribute of table type CDR_NAMING_VERSION_OBJ_TYPE.
 - * **Company_ID** To get your company ID, use CDR_PUB_DEF_FACTORY_UTILS.GetCompanyId.
 - * **OBJECT_TYPE_RC** Enter the OBJECT_TYPE_RC as '\$OBJTYPES\$XFORMMAP'
 - * **NAMESPACE_OBJ_ID** Enter the object ID of the parent in which you want to create transformation map. Parent object ID will be study ID, model map ID and table map ID for creating a model, table and column map respectively.
 - * **NAMESPACE_OBJ_VER** Enter the parent object version in which you want to create transformation map: study version, model map version and table map version for creating a model, table and column map respectively.
 - **MAP_LEVEL** (Mandatory) Enter either: MODEL, TABLE, or COLUMN.
 - **MAP_TYPE** Enter Map_Type as '\$MAPTYPE\$DEFAULT' for transformation at model, table and column level.
 - **XFORM_TYPE** For model and column maps enter: '\$XFORMTYPE\$DIRECT'. For table level maps, enter one of the following values based on the table map type:
 - * \$XFORMTYPE\$DIRECT
 - * \$XFORMTYPE\$UNION
 - * \$XFORMTYPE\$JOIN
 - * \$XFORMTYPE\$CUSTOM
 - * \$XFORMTYPE\$PIVOT
 - * \$XFORMTYPE\$UNPIVOT

* \$XFORMTYPE\$CUSTOM

 Tip:

Specify the type of transformation that your custom program actually does, if possible. Use the value \$XFORMTYPE\$CUSTOM only if the transformation does not do any of the other transformation types. This is to support data lineage tracing.

- **PROGRAM_TYPE** When creating a table-level map for a transformation with \$XFORMTYPE\$CUSTOM, enter either SYSTEM or CUSTOM, depending on the program source. Otherwise enter null.
- **PROGRAM_ID** Enter Program Obj_Id while creating a table level map of transformation type as '\$XFORMTYPE\$CUSTOM', otherwise, enter null.
- **PROGRAM_VER** Enter Program Obj_Ver while creating a table level map of transformation type as '\$XFORMTYPE\$CUSTOM', otherwise, enter null.
- **PIVOT_COLUMN_ID** Enter Object Id of the pivot column while creating a table transformations of pivot type, otherwise, enter null.
- **PIVOT_COLUMN_VER** Enter Object Version of the pivot column while creating a table transformations of pivot type, otherwise, enter null.
- **OPERATION_TYPE** Enter operation type as '\$OPER\$CREATE'.
- **MAP_ENTITY_COLL** This attribute is a collection of DME_MAP_ENTITY_OBJ_TYPE object type attributes. The following attributes are required:
 - * **DATA_ENTITY_ID** For transformation map at model level, enter Source Data Model Object Id for Source Map Entity and Target Data Model Object ID for Target Map Entity.
For transformation map at table level, enter Source Table Definition Object Id for Source Map Entity and Target Table Definition Object ID for Target Map Entity.
For transformation map at column level, enter Source Column Object Id for Source Map Entity and Target Column Object ID for Target Map Entity.

 Tip:

If you are mapping multiple tables or columns, pass the source and target Object IDs through a loop to enter values one after the other and commit to the database at the end.

- * **DATA_ENTITY_VER** Enter Object Version corresponding to the object selected for DATA_ENTITY_ID population.
- * **MAP_RELATION** Map_relation should be passed as 'SOURCE' for source map entities and 'TARGET' for target map entities.
- * **EXPR_OBJ_TYPE** This parameter is a object type of DME_XFORM_EXPR_OBJ_TYPE. Pass the expression details for source filter for source tables in case of table level transformations. Refer to the following section [Create or Modify an Expression](#), for more details.
- * **OPERATION_TYPE** The operation type should be passed as '\$OPER\$CREATE' for all source and target entities.

- **JOIN_COLL** This is a parameter of collection type CDR_DM_JOIN_OBJ_COLL and CDR_DM_JOIN_OBJ_COLL is table of CDR_DM_JOIN_OBJ_TYPE object type. This collection is required for creating table level transformations of 'Join' Type. The following attributes are required for join transformations:
 - * COMPANY_ID - Company Id
 - * TAB_COMPANY_ID -Table Company Id
 - * TAB_OBJ_ID - Table Obj Id
 - * TAB_ALIAS - Table Alias
 - * FK_TAB_COMPANY_ID - Enter the Company ID of the foreign key table.
 - * FK_TAB_OBJ_ID - Enter the Object ID of the foreign key table.
 - * FK_TAB_ALIAS - Alias for second table
 - * TD_OUTERJOIN_RC- Set to '\$YESNO\$YES' if outer joined defined on first table, otherwise '\$YESNO\$NO'.
 - * FK_TD_OUTERJOIN_RC- Set to '\$YESNO\$YES' if outer joined defined on second table, otherwise '\$YESNO\$NO'.
 - * DM_JOIN_COL_OBJ_COLL - This is a parameter of collection type CDR_DM_JOIN_COL_OBJ_COLL and CDR_DM_JOIN_COL_OBJ_COLL is table of CDR_DM_JOIN_COL_OBJ_TYPE object type. This collection is required for populating the join conditions. The attributes required for this API are:
 - * COMPANY_ID - Company Id
 - * TAB_COMPANY_ID -Table Company Id
 - * TAB_OBJ_ID - Table Obj Id
 - * TAB_ALIAS - Table Alias
 - * TAB_COL_COMPANY_ID -Joined Table Column Company Id
 - * TAB_COL_OBJ_ID - Table Column Obj Id
 - * FK_TAB_COMPANY_ID - Second table company Id which is joined with first table
 - * FK_TAB_OBJ_ID - Second table obj Id which is joined with first table
 - * FK_TAB_ALIAS - Alias for second table
 - * FK_TAB_COL_COMPANY_ID -Table Column Company Id from second table which is joined with first table
 - * FK_TAB_COL_OBJ_ID - Table Column Obj Id from second table which is joined with first table
 - * POSITION - Sequence of join condition. The sequence should start for first join condition from 1.
 - * JOIN_OPERATOR_RC - This refers to type of join condition. This can have the following values:
 - \$JOINOPER\$EQUALS
 - \$JOINOPER\$EQUALS
 - \$JOINOPER\$GREATER
 - \$JOINOPER\$GREATEREQUAL
 - \$JOINOPER\$LESS
 - \$JOINOPER\$LESSEQUAL

\$JOINOPER\$NOTEQUALS

Modify Transformation Maps

Use this API to modify model, table and column level transformation maps.

Name

DME_PUB_XFORM_MAP.ModifyTransformationMap

Signature

```

PROCEDURE MODIFYTRANSFORMATIONMAP
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PIO_XFORMMAP IN OUT
NOCOPY DME_XFORM_MAP_EX_OBJ_TYPE,
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_XFORMMAP** (Mandatory). This is a parameter of DME_XFORM_MAP_EX_OBJ_TYPE object type. The attributes required for this API are:
 - **NAMING** This is an attribute of table type CDR_NAMING_VERSION_OBJ_TYPE.
 - * **Company_ID** To get your company ID, use CDR_PUB_DEF_FACTORY_UTILS.GetCompanyId.
 - * **OBJECT_TYPE_RC** Enter the OBJECT_TYPE_RC as '\$OBJTYPES\$XFORMMAP'
 - * **NAMESPACE_OBJ_ID** Enter the object ID of the parent in which you want to create transformation map. Parent object ID will be study ID, model map ID and table map ID for creating a model, table and column map respectively.
 - * **NAMESPACE_OBJ_VER** Enter the parent object version in which you want to create transformation map: study version, model map version and table map version for creating a model, table and column map respectively.
 - **MAP_LEVEL** (Mandatory) Enter either: MODEL, TABLE, or COLUMN.
 - **MAP_TYPE** Enter Map_Type of the transformation map. It can be specified as '\$MAPTYPE\$DEFAULT'.
 - **XFORM_TYPE** Enter map_Type of transformation map being modified. For table map, same of modified map type can be:
 - * \$XFORMTYPE\$DIRECT
 - * \$XFORMTYPE\$UNION
 - * \$XFORMTYPE\$JOIN
 - * \$XFORMTYPE\$CUSTOM
 - * \$XFORMTYPE\$PIVOT
 - * \$XFORMTYPE\$UNPIVOT
 - * \$XFORMTYPE\$CUSTOM

**Tip:**

Specify the type of transformation that your custom program actually does, if possible. Use the value \$XFORMTYPE\$CUSTOM only if the transformation does not do any of the other transformation types. This is to support data lineage tracing.

- **PROGRAM_TYPE** Enter either: SYSTEM or CUSTOM.
- **PROGRAM_ID** Enter the program object id, if table level transformation of custom type being modified, otherwise NULL.
- **PROGRAM_VER** Enter the program object version, if table level transformation of custom type being modified, otherwise NULL.
- **PIVOT_COLUMN_ID** Enter Object Id of a Column, if table level pivot transformations being modified, otherwise NULL.
- **PIVOT_COLUMN_VER** Enter Object Version of a Column, if table level pivot transformations being modified, otherwise NULL.
- **OPERATION_TYPE** Enter operation type as '\$OPER\$MODIFY'.
- **MAP_ENTITY_COLL** This attribute is a collection of DME_MAP_ENTITY_OBJ_TYPE object type attributes. All attributes are required including identifying attributes along with required modifications. The operation_type should be passed as '\$OPER\$CREATE', '\$OPER\$MODIFY' or '\$OPER\$REMOVE' depending upon the modification required for a map entity.

The EXPR_OBJ_TYPE is one of the attribute in DME_MAP_ENTITY_OBJ_TYPE object type. This is a object type of DME_XFORM_EXPR_OBJ_TYPE. Pass the expression details for source filter for table level transformations. Refer to [Create or Modify an Expression](#), for details.

- **JOIN_COLL** - This is a parameter of collection type CDR_DM_JOIN_OBJ_COLL and CDR_DM_JOIN_OBJ_COLL is a table of CDR_DM_JOIN_OBJ_TYPE object type. This collection is required for modifying table level transformations of 'Join' Type. The attributes of CDR_DM_JOIN_OBJ_TYPE required for this API, including the modifications which are required in the join condition, are:
 - COMPANY_ID
 - OBJ_ID
 - OBJ_VER
 - TABLE_NAME
 - FK_TABLE_NAME
 - TAB_COMPANY_ID
 - TAB_OBJ_ID
 - TAB_ALIAS
 - TAB_MAP_ENTITY_ID
 - FK_TAB_COMPANY_ID
 - FK_TAB_OBJ_ID
 - FK_TAB_ALIAS
 - FK_TAB_MAP_ENTITY_ID

- TD_OUTERJOIN_RC
- FK_TD_OUTERJOIN_RC
- DM_JOIN_COL_OBJ_COLL

The DM_JOIN_COL_OBJ_COLL attribute is a parameter of collection type CDR_DM_JOIN_COL_OBJ_COLL, and CDR_DM_JOIN_OBJ_COLL is table of CDR_DM_JOIN_COL_OBJ_TYPE object type.

The attributes of CDR_DM_JOIN_COL_OBJ_TYPE required for this API, including the modifications which are required in the join condition, are:

- COMPANY_ID
- DM_JOIN_OBJ_ID
- DM_JOIN_OBJ_VER
- TAB_COMPANY_ID
- TAB_OBJ_ID
- TAB_ALIAS
- TABLE_NAME
- TAB_COL_COMPANY_ID
- TAB_COL_OBJ_ID
- TABLE_COLUMN_NAME
- FK_TAB_COMPANY_ID
- FK_TAB_OBJ_ID
- FK_TAB_ALIAS
- FK_TABLE_NAME
- FK_TAB_COL_COMPANY_ID
- FK_TAB_COL_OBJ_ID
- FK_TABLE_COL_NAME
- POSITION
- JOIN_OPERATOR_RC

The JOIN_OPERATOR_RC refers to type of join condition. This can have the following values:

- \$JOINOPER\$EQUALS
- \$JOINOPER\$EQUALS
- \$JOINOPER\$GREATER
- \$JOINOPER\$GREATEREQUAL
- \$JOINOPER\$LESS
- \$JOINOPER\$LESSEQUAL
- \$JOINOPER\$NOTEQUALS

Mark Table Maps Not Used

Use this API to mark table mappings as Not Used.

Name

DME_PUB_XFORM_MAP.MarkTableMapNotUsed

Signature

```
PROCEDURE MARKTABLEMAPNOTUSED
( P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
  X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PI_MAPOBJID IN
  CDR_NAMING_VERSIONS.OBJ_ID%TYPE, PI_MAPOBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_MAPOBJID** (Mandatory). Enter object Id of Table Transformation Map.
- **PI_MAPOBJVER** (Mandatory). Enter object Version of Table Transformation Map.

Mark Column Maps Not Used

Use this API to mark column mappings as Not Used.

Name

DME_PUB_XFORM_MAP.MarkColumnMapNotUsed

Signature

```
PROCEDURE MARKCOLUMNMAPNOTUSED
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
  X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PI_MAPOBJID IN
  CDR_NAMING_VERSIONS.OBJ_ID%TYPE, PI_MAPOBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_MAPOBJID** (Mandatory). Enter object Id of Column Transformation Map.
- **PI_MAPOBJVER** (Mandatory). Enter object Version of Column Transformation Map.

Check In Transformation Maps

Use this API to check in the given transformation map.

Name

DME_PUB_XFORM_MAP.CheckinTransformationMap

Signature

```
PROCEDURE CHECKINTRANSFORMATIONMAP
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PIO_NAMING IN OUT
NOCOPY CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory). This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the transformation map that you want to check in. The following attributes are required:
 - COMPANY_ID
 - OBJ_ID
 - OBJ_VER
 - NAMESPACE_OBJ_ID
 - NAMESPACE_OBJ_VER
 - OBJECT_VERSION_NUMBER

Check Out Transformation Maps

Use this API to check out the given transformation map.

Name

DME_PUB_XFORM_MAP.CheckoutTransformationMap

Signature

```
PROCEDURE CHECKOUTTRANSFORMATIONMAP
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PIO_NAMING IN OUT
NOCOPY CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory). This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the transformation map. The attributes for this API are:
 - COMPANY_ID
 - OBJ_ID
 - OBJ_VER

- NAMESPACE_OBJ_ID
- NAMESPACE_OBJ_VER
- OBJECT_VERSION_NUMBER

Undo Checkout Transformation Map

Use this API to undo check out the given transformation map.

Name

DME_PUB_XFORM_MAP.UndoCheckoutTransformationMap

Signature

```
PROCEDURE UNDOCHECKOUTTRANSFORMATIONMAP
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PIO_NAMING IN OUT
NOCOPY CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_NAMING (Mandatory). This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the transformation map.

The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER, NAMESPACE_OBJ_ID, NAMESPACE_OBJ_VER, OBJECT_VERSION_NUMBER.

Auto Map Tables

Use this API to create candidate auto Maps for table & Column transformation mappings. This operation accepts the target data model identifier object details as parameter for which auto maps has to be generated. The API creates the potential auto maps based on Oracle Name, Data Type & Length and Alias Match.

Name

DME_PUB_XFORM_MAP.AutoMapTables

Signature

```
PROCEDURE AUTOMAPTABLES
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PI_DATAENTITYID IN
CDR_NAMING_VERSIONS.OBJ_ID%TYPE, PI_DATAENTITYVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_DATAENTITYID** (Mandatory). Enter the object Id of the model transformation map on which auto map has to be performed.
- **PI_DATAENTITYVER** (Mandatory). Enter the object Version of the model transformation map on which auto map has to be performed.

Accept Table Mappings

Use this API to create persistent Auto Maps by accepting the auto generated table and column transformation mappings created from `dme_pub_xform_map.autoMapTables` public API. User refers to `DME_PUB_XFM_AUTOMAPS_V` view to populate the attributes of input collection required as a parameter.

Name

DME_PUB_XFORM_MAP.AcceptTableAutoMappings

Signature

```
PROCEDURE ACCEPTTABLEAUTOMAPPINGS
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PIO_TABLEAUTOMAPCOLL IN
OUT NOCOPY DME_XFORM_AUTO_MAP_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_TABLEAUTOMAPCOLL** (Mandatory). This is a parameter of table type collection `DME_XFORM_AUTO_MAP_COLL` of `DME_XFORM_AUTO_MAP_TYPE` table type. All attributes are required including:
 - COMPANY_ID
 - MAP_ID
 - MAP_VER
 - MAP_ENTITY_ID
 - MAP_ENTITY_VER
 - CANDIDATE_FLAG_RC - with the possible values:
 - * \$YESNO\$YES
 - * \$YESNO\$NO - use this value for auto map suggestions which are applicable to save as real maps.

Auto Map Columns

Use this API to create candidate auto Maps for Column transformation mappings. This operation accepts the target table object identifier details as parameter for which auto maps has to be generated. The API creates the potential auto maps based on Oracle Name, Data Type & Length and Alias Match.

Name

DME_PUB_XFORM_MAP.AutoMapColumns

Signature

```
PROCEDURE AUTOMAPCOLUMNS
( P_API_VERSION IN VARCHAR2,    P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
  X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PI_DATAENTITYID IN
  CDR_NAMING_VERSIONS.OBJ_ID%TYPE, PI_DATAENTITYVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_DATAENTITYID** (Mandatory). Enter the object Id of the target table on which auto map has to be performed.
- **PI_DATAENTITYVER** (Mandatory). Enter the object Version of the target table.

Get MappedTo Target Columns

Use this API to find all the target columns for particular source column in a table map.

Name

DME_PUB_XFORM_MAP.GetMappedToTargetColumns

Signature

```
PROCEDURE GetMappedToTargetColumns (
  p_api_version IN NUMBER,
  p_init_msg_list IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE,
  p_commit IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE,
  p_validation_level IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
  x_return_status      OUT NOCOPY  VARCHAR2,
  x_msg_count          OUT NOCOPY  NUMBER,
  x_msg_data           OUT NOCOPY  VARCHAR2,
  p_companyId in cdr_namings.company_id%type,
  pi_tabMapId in cdr_namings.obj_id%type,
  pi_tabMapVer in cdr_naming_versions.obj_ver%type,
  pi_columnId in cdr_namings.obj_id%type,
  pi_columnVer in cdr_naming_versions.obj_ver%type,
  po_targetColumnsColl OUT NOCOPY  dme_char_coll
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **P_COMPANYID** (Mandatory). Enter the company ID of the object.
- **PI_TABMAPID** (Mandatory). Enter the table map object ID.
- **PI_TABMAPVER** (Mandatory). Enter the table map object version.
- **PI_COLUMNID** (Mandatory). Enter the column object ID.

- **PI_COLUMNVER** (Mandatory). Enter the column object version.
- **PO_TARGETCOLUMNSCOLL**. Output collection of target columns in the format of `Model_NAME.Table_NAME.Column_NAME`.

Accept Column Mappings

Use this API to create persistent Auto Maps by accepting the auto generated column transformation mappings.

Name

DME_PUB_XFORM_MAP.AcceptColumnAutoMappings

Signature

```
PROCEDURE ACCEPTCOLUMNAUTOMAPPINGS
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PIO_COLUMNAUTOMAPCOLL
IN OUT NOCOPY DME_XFORM_AUTO_MAP_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PIO_COLUMNAUTOMAPCOLL (Mandatory). This is a parameter of table type collection `DME_XFORM_AUTO_MAP_COLL` of `DME_XFORM_AUTO_MAP_TYPE` table type. All attributes are required including:

- **COMPANY_ID**
- **MAP_ID**
- **MAP_VER**
- **MAP_ENTITY_ID**
- **MAP_ENTITY_VER**
- **CANDIDATE_FLAG_RC** - with the possible values:
 - **\$YESNO\$YES**
 - **\$YESNO\$NO** - use this value for auto map suggestions which are applicable to save as real maps.

Upgrade Transformation Map

Use this API to upgrade the maps defined at model level.

Name

DME_PUB_XFORM_MAP.UpgradeXformMap

Signature

```
PROCEDURE UPGRADEXFORMMAPS
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
```

```

CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_XFORMMAPCOMPID** (Mandatory). Enter the COMPANY_ID for the transformation map to be upgraded.
- **PI_XFORMMAPOBJID** (Mandatory). Enter the OBJ_ID for the transformation map to be upgraded.
- **PI_XFORMMAPOBJVER** (Mandatory). Enter the OBJ_VER for the transformation map to be upgraded.

Install Transformation Map

Use this API to install transformation mappings.

Name

DME_PUB_XFORM_MAP.InstallXform

Signature

```

PROCEDURE INSTALLXFORM
( P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PI_MAPCOMPANYID IN
CDR_NAMINGS.COMPANY_ID%TYPE, PI_MAPOBJID IN CDR_NAMINGS.OBJ_ID%TYPE, PI_MAPOBJVER
IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE, PI_CONTEXT IN VARCHAR2 DEFAULT
'$LIFECYCLE$DEV', PO_JOBID OUT NOCOPY CDR_JOBS.JOB_ID%TYPE
);

```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_MAPCOMPANYID** (Mandatory). Enter values for the company Id for Model Transformation Map.
- **PI_MAPOBJID** (Mandatory). Enter values for the object Id for Model Transformation Map.
- **PI_MAPOBJVER** (Mandatory). Enter values for the object Version for Model Transformation Map.
- **PI_CONTEXT** (Mandatory). Enter values for the lifecycle context. The possible values are:
 - \$LIFECYCLE\$DEV (also the default value)
 - \$LIFECYCLE\$QC
 - \$LIFECYCLE\$ PROD
- **PO_JOBID** This is the out parameter as job id generated from installation of given transformation map. Installation of Transformation Mapping submits a job. So this output parameter returns a JOB_ID for Transformation Mapping Batch installation.

Remove Transformation Map

Use this API to remove the transformation map at Model, Table or Column Level.

Name

DME_PUB_XFORM_MAP.RemoveTransformationMap

Signature

```
PROCEDURE REMOVETRANSFORMATIONMAP
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PIO_NAMING IN OUT
NOCOPY CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_NAMING (Mandatory). This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the transformation map. The following attributes are required:

- COMPANY_ID
- OBJ_ID
- OBJ_VER

Validate Transformation Maps

Use this API to validate the transformation maps defined at model and table level. If a transformation map is invalid, the status of transformation map is invalidated to 'Invalid', description field is updated with validation errors and red icon is shown on UI corresponding to invalid transformation maps.

Name

DME_PUB_XFORM_MAP.ValidateXform

Signature

```
PROCEDURE VALIDATEXFORM
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PIO_NAMING IN OUT
NOCOPY CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameter:

PIO_NAMING (Mandatory). This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the transformation map. The following attributes are required:

- COMPANY_ID
- OBJ_ID
- OBJ_VER

Update Validation Status

Use this API to modify the validation status.

Name

DME_PUB_XFORM_MAP.UpdateValStatus

Signature

```
PROCEDURE UPDATEVALSTATUS
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PIO_NAMING IN OUT
NOCOPY CDR_NAMING_VERSION_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

PIO_NAMING (Mandatory). This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. All attributes are required including:

- COMPANY_ID
- OBJ_ID
- OBJ_VER
- NAMESPACE_OBJ_ID
- NAMESPACE_OBJ_VER
- OBJECT_TYPE_RC
- CHECKED_OUT_FLAG_RC
- VALIDATION_STATUS_RC

The new validation status should be assigned to field VALIDATION_STATUS_RC. The possible valid values for validation status are:

- \$SYSVALDNSTEPS\$DEVELOPMENT
- \$SYSVALDNSTEPS\$QUALITYCONTROL
- \$SYSVALDNSTEPS\$PRODUCTION
- \$SYSVALDNSTEPS\$RETIRED

Execute Transformation Map

Use this API to execute a Transformation Map.

Name

DME_PUB_XFORM_MAP.ExecuteXform

Signature

```
PROCEDURE EXECUTEXFORM
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PI_MODELCOMPANYID IN
CDR_NAMINGS.COMPANY_ID%TYPE, PI_MODELOBJID IN CDR_NAMINGS.OBJ_ID%TYPE, PI_MODELOBJVER
IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE, PI_SUBMISSION_TYPE IN VARCHAR2 DEFAULT
'$SUBMISSTYPES$IMMEDIATE', PI_CONTEXT IN VARCHAR2 DEFAULT '$LIFECYCLE$DEV',
PI_SCHED_START_TS IN DATE DEFAULT NULL, PI_SCHED_END_TS IN DATE DEFAULT NULL,
PI_SCHED_REPEAT_INTERVAL IN VARCHAR2 DEFAULT NULL, PI_SCHED_REPEAT_LIST IN VARCHAR2
DEFAULT NULL, PI_FORCE_EXECUTION_FLAG_RC IN VARCHAR2 DEFAULT '$YESNO$NO',
PI_RUN_MODE_RC IN VARCHAR2, PI_TRIGGER_DOWNSTREAM IN VARCHAR2, PO_JOBID OUT NOCOPY
CDR_JOBS.JOB_ID%TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_MODELCOMPANYID** (Mandatory). Company id of Target Data Model.
- **PI_MODELOBJID** (Mandatory). Object Id of Target Data Model.
- **PI_MODELOBJVER** (Mandatory). Object Version of Target Data Model
- **PI_SUBMISSION_TYPE**. Enter '\$SUBMISSTYPES\$IMMEDIATE' or '\$SUBMISSTYPES\$SCHEDULED' or '\$SUBMISSTYPES\$DEFERRED'.
- **PI_CONTEXT**. Lifecycle context values like \$LIFECYCLE\$DEV, \$LIFECYCLE\$QC or \$LIFECYCLE\$PROD.
- **PI_SCHED_START_TS**. Enter start time if submission is scheduled/deferred.
- **PI_SCHED_END_TS**. Enter end time if submission is scheduled.
- **PI_SCHED_REPEAT_INTERVAL**. Enter interval time if submission is scheduled.
- **PI_SCHED_REPEAT_LIST**. Enter Unit like Hour(s), Day(s), Week(s).
- **PI_FORCE_EXECUTION_FLAG_RC**. Enter '\$YESNO\$NO' or '\$YESNO\$YES'.
- **PI_RUN_MODE_RC**. Enter '\$RUNMODES\$FULL' or '\$RUNMODES\$INCREMENT'.
- **PI_TRIGGER_DOWNSTREAM**. Enter '\$YESNO\$YES' or '\$YESNO\$NO'.

Validate Expression

Use this API to validate user defined map column or criteria expression.

Name

DME_PUB_XFORM_MAP.ValidateExpression

Signature

```
PROCEDURE VALIDATEEXPRESSION
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PI_OBJID IN
CDR_NAMINGS.OBJ_ID%TYPE, PI_OBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE, PI_EXPROBJ IN
DME_XFORM_EXPR_OBJ_TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_OBJID** (Mandatory). Enter the object Id of the model transformation map in which expression is applied for one of the map entity. In case of Create operations, map will not exist in DB. Pass the table definition id from which column has been selected into the expression. Pass NULL, in case, no column is used in expression text.
- **PI_OBJVER** (Mandatory). Enter the object Version of the model transformation map or table definition from which column is used in expression. Pass NULL, in case there is no column used in expression.
- **PI_EXPROBJ** (Mandatory). This parameter is a object type of DME_XFORM_EXPR_OBJ_TYPE. Refer to the following section [Create or Modify an Expression](#), for more details.

Refresh Static Packages

Run this API after you add, modify, or delete a static package to be used in a transformation or validation check. This is required for the changes to take effect.

Name

DME_PUB_XFORM_MAP.populateStaticPackages

Signature

```
PROCEDURE dme_pub_xform_map.populateStaticPackages
( p_api_version IN VARCHAR2
, p_init_msg_list IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE
, p_commit IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
, p_validation_level IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
, x_return_status OUT NOCOPY VARCHAR2
, x_msg_count OUT NOCOPY NUMBER
, x_msg_data OUT NOCOPY VARCHAR2);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)).

Validation Checks

This is a public interface for all operations related to Validation Checks Batch(es), including creation, deletion, modification, and checking in and out of these objects. It also includes information on how to create or modify expressions.

This section includes the Validation Checks APIs from the following package:
DME_PUB_VALIDATION_CHECK.

See [Refresh Static Packages](#) for information about the API you must run whenever you add, change, or delete a static package to be used in validation checks.

This chapter contains the following section:

- [Create and Modify Validation Checks and Batches](#)

Create and Modify Validation Checks and Batches

This section contains the following public APIs:

- [Create a Validation Check Batch](#)
- [Modify a Validation Check Batch](#)
- [Remove Validation Check Batch](#)
- [Create a Validation Check](#)
- [Update a Validation Check](#)
- [Install a Validation Check Batch](#)
- [Submit a Validation Check Batch](#)
- [Check In a Validation Check Batch](#)
- [Check Out a Validation Check Batch](#)
- [Undo Checkout For a Validation Check Batch](#)
- [Update Validation Status of a Validation Check Batch](#)
- [Upgrade a Validation Check Batch](#)
- [Remove Validation Check\(s\)](#)
- [Enable or Disable Validation Checks](#)
- [Reorder Validation Checks](#)

Create a Validation Check Batch

Use this API to create a validation check batch.

Name

DME_PUB_VALIDATION_CHECK.CreateValidationCheckBatch

Signature

```
PROCEDURE CREATEVALIDATIONCHECKBATCH,
( P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 default
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER default
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PI_SOURCEMODELCOMPID IN
OUT NOCOPY CDR_NAMINGS.COMPANY_ID%TYPE, PI_SOURCEMODELOBJID IN OUT NOCOPY
CDR_NAMINGS.OBJ_ID%TYPE, PI_SOURCEMODELOBJVER IN OUT NOCOPY
CDR_NAMING_VERSIONS.OBJ_VER%TYPE, PI_BATCHNAME IN OUT NOCOPY CDR_NAMINGS.NAME%TYPE,
PI_BATCHDESCRIPTION IN CDR_NAMING_VERSIONS.DESCRPTION%TYPE, PI_ISORDEREDFOREXECUTION
IN VARCHAR2, PI_CANBETRIGGERED IN VARCHAR DEFAULT '$YESNO$NO',
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_SOURCEMODELCOMPID** (Mandatory). Enter COMPANY_ID of Source Data Model.
- **PI_SOURCEMODELOBJID** (Mandatory). Enter the obj_id of the table instance which contains the data record.
- **PI_SOURCEMODELOBJVER** (Mandatory). Enter OBJ_VER of Source Data Model.
- **PI_BATCHNAME** (Mandatory). Enter Batch Name for new VC Batch.
- **PI_BATCHDESCRIPTION** (Optional). Enter Batch Description if you want for new VC Batch.
- **PI_ISORDEREDFOREXECUTION** (Optional). Enter \$YESNO\$YES, if Validation Checks under new Batch must be executed in particular order. Otherwise enter \$YESNO\$NO. If entered as NULL, systems defaults it to \$YESNO\$NO.
- **PI_CANBETRIGGERED** (Mandatory). Enter \$YESNO\$YES. This allows the successful completion of a transformation writing to the clinical data model that this batch runs against to trigger the execution of this batch. Entering a different value may result in unexpected behavior.

Modify a Validation Check Batch

Use this API to modify a validation check batch.

Name

DME_PUB_VALIDATION_CHECK.UpdateValidationCheckBatch

Signature

```
PROCEDURE UPDATEVALIDATIONCHECKBATCH
( P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PI_BATCHMAPCOMPID IN
OUT NOCOPY CDR_NAMINGS.COMPANY_ID%TYPE, PI_BATCHMAPOBJID IN OUT NOCOPY
CDR_NAMINGS.OBJ_ID%TYPE, PI_BATCHMAPOBJVER IN OUT NOCOPY
CDR_NAMING_VERSIONS.OBJ_VER%TYPE, PI_BATCHNAME IN OUT NOCOPY CDR_NAMINGS.NAME%TYPE,
PI_BATCHDESCRIPTION IN CDR_NAMING_VERSIONS.DESCRPTION%TYPE, PI_ISORDEREDFOREXECUTION
IN VARCHAR2, PI_CANBETRIGGERED IN VARCHAR DEFAULT '$YESNO$NO'
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_BATCHMAPCOMPID** (Mandatory). Enter COMPANY_ID of Validation Checks Batch Map.
- **PI_BATCHMAPOBJID** (Mandatory). Enter OBJ_ID of Validation Checks Batch Map.
- **PI_BATCHMAPOBJVER** (Mandatory). Enter OBJ_VER of Validation Checks Batch Map.
- **PI_BATCHNAME** (Mandatory). Enter Batch Name for new Validation Checks Batch
- **PI_BATCHDESCRIPTION** (Optional). Enter Batch Description for new Validation Checks Batch.
- **PI_ISORDEREDFOREXECUTION** (Optional). Enter \$YESNO\$YES, if Validation Checks under new Batch must be executed in particular order. Otherwise enter \$YESNO\$NO. If entered as NULL, systems defaults it to \$YESNO\$NO.
- **PI_CANBETRIGGERED** (Optional). Enter \$YESNO\$YES to allow the successful completion of a transformation writing to the clinical data model that this batch runs against to trigger the execution of this batch. Otherwise enter \$YESNO\$NO. If entered as NULL, systems defaults it to \$YESNO\$NO.

Remove Validation Check Batch

Use this API to remove Validation Check batch(es).

Name

DME_PUB_VALIDATION_CHECK.RemoveValidationCheckBatches

Signature

```
PROCEDURE REMOVEVALIDATIONCHECKBATCHES
  (P_API_VERSION IN VARCHAR2,    P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
  X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PIO_VC_BATCH_COLL
  IN OUT NOCOPY CDR_NAMING_LIST_COLL
  );
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_VC_BATCH_COLL** (Mandatory). This is a parameter of collection type CDR_NAMING_LIST_COLL that contains CDR Naming Version attributes. The following attributes are required for Validation Checks Batch maps:
 - COMPANY_ID
 - OBJ_ID
 - OBJ_VER

Create a Validation Check

Use this API to create a validation check.

Name

DME_PUB_VALIDATION_CHECK.CreateValidationCheck

Signature

```
PROCEDURE createValidationCheck (
    p_api_version IN VARCHAR2
    , p_init_msg_list IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE
    , p_commit IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
    , p_validation_level IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
    , x_return_status OUT NOCOPY VARCHAR2
    , x_msg_count OUT NOCOPY NUMBER
    , x_msg_data OUT NOCOPY VARCHAR2
    , pi_xFormMapColl in out nocopy dme_xform_map_ex_coll
    , pi_vcBatchModelObj in cdr_base_obj_type
    , pi_VcSecondaryVarColl in dme_vc_secondary_var_obj_coll default null
    , pi_VcRunMode in VARCHAR2 default 'FULL'
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_XFORMMAPCOLL** (Mandatory). This is a parameter of collection type DME_XFORM_MAP_EX_COLL. DME_XFORM_MAP_EX_COLL is a table of DME_XFORM_MAP_EX_OBJ_TYPE. This collection is prepared with both Table level and Column Level maps. Validation Checks Details are set at Table level mapping.

The following attributes from DME_XFORM_MAP_EX_OBJ_TYPE are required for this API:

- NAMING: Table type CDR_NAMING_VERSION_OBJ_TYPE

For Table Level mapping and Validation Checks Create, mandatory attributes are:

- COMPANY_ID
- NAME - Refers to Validation Checks name
- OBJECT_TYPE_RC - Enter the value: '\$OBJTYPE\$XFORMMAP'.

For Column Level mapping and Validation Checks Create, mandatory attributes are:

- COMPANY_ID
- OBJECT_TYPE_RC - Enter the value: '\$OBJTYPE\$XFORMMAP'.
- **MAP_TYPE**. Enter '\$MAPTYPE\$VC'
- **XFORM_TYPE**. Enter '\$XFORMTYPE\$DIRECT' for single source table and '\$XFORMTYPE\$JOIN' for multiple source table.
- **PROGRAM_ID**. If the validation check uses a custom program, enter the Program obj_id, else leave blank.
- **PROGRAM_VER**. If the validation check uses a custom program, enter the Program obj_ver, else leave blank.
- **PROGRAM_TYPE**. 'CUSTOM' for Custom program. Else leave blank. When creating Validation Checks using Custom Program, column level maps are not required in the collection parameter (PI_XFORMMAPCOLL).

- **AUTH_FLAG_RC.** Enter '\$YESNO\$YES' to authorize Validation Checks listing to read blinded data. Otherwise leave blank. It defaults to '\$YESNO\$NO'.
- **OPERATION_TYPE.** '\$OPER\$CREATE' for Validation Checks create.
- **MAP_ENTITY_COLL.** Its collection type DME_MAP_ENTITY_COLL which is table of DME_MAP_ENTITY_OBJ_TYPE type.
For table level mapping, only source entities are required in MAP_ENTITY_COLL collection. Enter COMPANY_ID, DATAENTITY_ID, DATAENTITY_VER, MAP_RELATION as SOURCE, expression details (see [Create or Modify an Expression](#)), and OPERATION_TYPE as '\$OPER\$CREATE'.

For column level mapping, both source and target entities are required in MAP_ENTITY_COLL collection. For source entities, enter company_id, dataentity_id, dataentity_ver, map_relation as SOURCE, expression details and operation_type as '\$OPER\$CREATE' and for target entity, enter ALIAS, map_relation as TARGET and operation_type as '\$OPER\$CREATE'.
- **JOIN_COLL.** Required only for VC using multiple source tables. This is a collection of type CDR_DM_JOIN_OBJ_COLL. Set only in table level mapping.
CDR_DM_JOIN_OBJ_COLL is table of type CDR_DM_JOIN_OBJ_TYPE.

CDR_DM_JOIN_OBJ_TYPE is for Table Joins and set the source and target table ids. This object type has an attribute of collection type DM_JOIN_COL_OBJ_COLL for column joins.

DM_JOIN_COL_OBJ_COLL is table of type CDR_DM_JOIN_COL_OBJ_TYPE. Table and Column related fields are required along with JOIN_OPERATOR_RC. For POSITION enter 1.
- **VC_DETAILS.** Table of dme_val_check_details_obj_type. Set only in table level mapping.
COMPANY_ID, DISC_OPEN_STATE, DISCREPANCY_TEXT, PRIMARY_SOURCE_COLUMN_ID are mandatory.
AUTO_CLOSE_FLAG, CATEGORY_ID and INITIAL_DISC_ACTION_ID are optional.
 - * **DISC_OPEN_STATE.** Possible values are '\$DISC_STATES\$OPEN' and '\$DISC_STATES\$CANDIDATE'.
 - * **DISCREPANCY_TEXT.** Enter a text as comment for created discrepancies from Validation Checks.
 - * **PRIMARY_SOURCE_COLUMN_ID.** Source Column OBJ_ID on which discrepancy is created.
 - * **AUTO_CLOSE_FLAG.** Possible values are '\$YESNO\$YES' and '\$YESNO\$NO'. Enter '\$YESNO\$YES', if Validation Check can auto close the discrepancy.
 - * **CATEGORY_ID.** Enter a valid Validation Check category Id from DME_CATEGORIES.
 - * **INITIAL_DISC_ACTION_ID.** : If discrepancies need DM review, enter 31 when DISC_OPEN_STATE='\$DISC_STATES\$CANDIDATE' or enter 32 when DISC_OPEN_STATE='\$DISC_STATES\$OPEN'.
- **PI_VCBATCHMODELOBJ** (Mandatory). This is a parameter of table type CDR_BASE_OBJ_TYPE. Enter values to identify the Validation Checks Batch Model under which you want to create Validation Checks.
- **PI_VCSECONDARYVARCOLL** (Optional). This is a parameter of collection type DME_VC_SECONDARY_VAR_SECONDARY_VAR_OBJ and DME_VC_SECONDARY_VAR_OBJ_COLL is a table type of DME_VC_SECONDARY_VAR_OBJ_TYPE. Enter the validation check column details where you want to set the secondary flag variable as Yes. Mandatory attribute types are:

- **DM_COL_OBJ_ID** - Add the source column object ID that mapped to the validation check column.
- **VC_COLUMN_NAME** - Enter the validation check display column name.

 Note:

This only applies to validation checks created without a custom program. For custom validation checks, define the secondary columns in Oracle LSH by adding **\$DMWVCSECONDARYVAR\$** at the end of any text in the **Description** field of the target table column. (Or, just add it to the **Description** field without any other text.)

- **PI_VCRUNMODE** (Optional). Enter "FULL" for All Source Data and "INCR" for New OR Updated Source Data. The default value is "FULL".

Update a Validation Check

Use this API to update a validation check.

Name

DME_PUB_VALIDATION_CHECK.UpdateValidationCheck

Signature

```
PROCEDURE updateValidationCheck (
    p_api_version IN VARCHAR2
    , p_init_msg_list IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE
    , p_commit IN VARCHAR2 default CDR_PUB_DEF_CONSTANTS.G_FALSE
    , p_validation_level IN NUMBER default CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
    , x_return_status OUT NOCOPY VARCHAR2
    , x_msg_count OUT NOCOPY NUMBER
    , x_msg_data OUT NOCOPY VARCHAR2
    , pi_xFormMapColl in out nocopy dme_xform_map_ex_coll
    , pi_vcSecondaryVarColl in dme_vc_secondary_var_obj_coll default null
    , pi_vcRunMode in VARCHAR2 default 'FULL'
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_XFORMMAPCOLL** (Mandatory). This is a parameter of collection type **DME_XFORM_MAP_EX_COLL** and **DME_XFORM_MAP_EX_COLL** is table of **DME_XFORM_MAP_EX_OBJ_TYPE**. This collection is prepared with both Table level and Column Level maps. Validation Check Details are set at Table level mapping.

The attributes required for this API from **DME_XFORM_MAP_EX_OBJ_TYPE** are:

- For Table Level mapping, all the attributes are required. Name refers to Validation Checks name and enter **OBJECT_TYPE_RC = '\$OBJTYPES\$XFORMMAP'**.
- For Column Level mapping all the attributes are required. Enter **OBJECT_TYPE_RC = '\$OBJTYPES\$XFORMMAP'**.
- **MAP_TYPE**. Enter **'\$MAPTYPE\$VC'**.

- **XFORM_TYPE.** Enter '\$XFORMTYPE\$DIRECT' for single source table and '\$XFORMTYPE\$JOIN' for multiple source table.
- **PROGRAM_ID.** Enter Custom Program Obj_Id when Create Validation Checks using custom program. In other cases leave blank.
- **PROGRAM_VER.** Enter Custom Program Obj_Ver when Create Validation Checks using custom program. In other cases leave blank.
- **PROGRAM_TYPE.** Write 'CUSTOM' for Custom program, else leave blank. When creating Validation Checks using Custom Program, column level maps are not required in the collection parameter (PI_XFORMMAPCOLL).
- **AUTH_FLAG_RC.** Enter '\$YESNO\$YES' to authorize Validation Checks listing to read blinded data. Otherwise leave blank. It defaults to '\$YESNO\$NO'.
- **OPERATION_TYPE.** '\$OPER\$MODIFY' for Validation Checks modify.
- **MAP_ENTITY_COLL.** It's collection type DME_MAP_ENTITY_COLL which is table of DME_MAP_ENTITY_OBJ_TYPE type. Leave blank, if you do not want to update anything.
For table level, enter both source and target entities with entity identifiers, data_entity indentifiers, map_relation as SOURCE or TARGET, expression details (see [Create or Modify an Expression](#).) for source and operation type as '\$OPER\$MODIFY'.

For column level:

1. Adding a new column, both source and target entities are required in MAP_ENTITY_COLL collection. For source entities, enter COMPANY_ID, DATAENTITY_ID, DATAENTITY_VER, MAP_RELATION as SOURCE, expression details (see [Create or Modify an Expression](#).) and operation_type as '\$OPER\$CREATE' and for target entity, enter ALIAS, map_relation as TARGET and operation_type as '\$OPER\$CREATE'.
 2. Updating a column, both source and target entities are required in MAP_ENTITY_COLL collection. For source entities, enter COMPANY_ID, MAP_ENTITY_ID, MAP_ENTITY_VER, DATAENTITY_ID, DATAENTITY_VER, MAP_RELATION as SOURCE, expression details (see [Create or Modify an Expression](#).) and operation_type as '\$OPER\$MODIFY' and for target entity, COMPANY_ID, MAP_ENTITY_ID, MAP_ENTITY_VER, DATAENTITY_ID, DATAENTITY_VER, enter ALIAS, MAP_RELATION as TARGET and operation_type as '\$OPER\$MODIFY'.
 3. Removing a column, both source and target entities are required in MAP_ENTITY_COLL collection. For both source and target entity, enter COMPANY_ID, MAP_ENTITY_ID, MAP_ENTITY_VER, DATAENTITY_ID, DATAENTITY_VER, MAP_RELATION as SOURCE or TARGET and OPERATION_TYPE as '\$OPER\$REMOVE'.
- **JOIN_COLL.** Leave blank, if you do not want to update anything. Required only for Validation Checks using multiple source tables. This is a collection of type CDR_DM_JOIN_OBJ_COLL. Set only in table level mapping.
CDR_DM_JOIN_OBJ_COLL is table of type CDR_DM_JOIN_OBJ_TYPE.
CDR_DM_JOIN_OBJ_TYPE is for Table Joins and set the source and target table ids. This object type has an attribute of collection type DM_JOIN_COL_OBJ_COLL for column joins.
DM_JOIN_COL_OBJ_COLL is table of type CDR_DM_JOIN_COL_OBJ_TYPE. Table and Column related fields are required along with JOIN_OPERATOR_RC. For POSITION enter 1.

- **VC_DETAILS.** Table of DME_VAL_CHECK_DETAILS_OBJ_TYPE. Set only in table level mapping. COMPANY_ID, DISC_OPEN_STATE, DISCREPANCY_TEXT, PRIMARY_SOURCE_COLUMN_ID are mandatory. AUTO_CLOSE_FLAG, CATEGORY_ID and INITIAL_DISC_ACTION_ID are optional. OBJ_ID and OBJ_VER are required only in case of Validation Checks update.
 - * DISC_OPEN_STATE: Possible values are '\$DISC_STATES\$OPEN' and '\$DISC_STATES\$CANDIDATE'.
 - * DISCREPANCY_TEXT: Enter a text as comment for created discrepancies from Validation Checks.
 - * PRIMARY_SOURCE_COLUMN_ID: Source Column OBJ_ID on which discrepancy is created.
 - * AUTO_CLOSE_FLAG: Possible values are '\$YESNO\$YES' and '\$YESNO\$NO'. Enter '\$YESNO\$YES', if Validation Checks can auto close the discrepancy.
 - * CATEGORY_ID: Enter a valid Validation Checks category ID from DME_CATEGORIES.
 - * INITIAL_DISC_ACTION_ID : If discrepancies need DM review, enter 31 when DISC_OPEN_STATE='\$DISC_STATES\$CANDIDATE' or enter 32 when DISC_OPEN_STATE='\$DISC_STATES\$OPEN'.
- **PI_VCSECONDARYVARCOLL** (Optional). This is a parameter of collection type DME_VC_SECONDARY_VAR_SECONDARY_VAR_OBJ and DME_VC_SECONDARY_VAR_OBJ_COLL is a table type of DME_VC_SECONDARY_VAR_OBJ_TYPE. Enter the validation check column details where you want to set the secondary flag variable as Yes. Mandatory attribute types are:
 - DM_COL_OBJ_ID - Add the source column object ID that mapped to the validation check column.
 - VC_COLUMN_NAME - Enter the validation check display column name.

 Note:

This only applies to validation checks created without a custom program. For custom validation checks, define the secondary columns in Oracle LSH by adding **\$DMWVCSECONDARYVAR\$** at the end of any text in the **Description** field of the target table column. (Or, just add it to the **Description** field without any other text.)

- **PI_VCRUNMODE** (Optional). Enter "FULL" for All Source Data and "INCR" for New or Updated Source Data. The default value is "FULL".

Install a Validation Check Batch

Use this API to install a validation check batch.

Name

DME_PUB_VALIDATION_CHECK.InstallValidationCheckBatch

Signature

```
PROCEDURE INSTALLVALIDATIONCHECKBATCH
(P_API_VERSION IN VARCHAR2,
```

```
P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_COMMIT IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER,
X_MSG_DATA OUT NOCOPY VARCHAR2,
PI_BATCHMAPCOMPID IN CDR_NAMINGS.COMPANY_ID%TYPE,
PI_BATCHMAPOBJID IN CDR_NAMINGS.OBJ_ID%TYPE,
PI_BATCHMAPOBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE,
PI_CONTEXT IN VARCHAR2 DEFAULT NULL,
PI_TESTMODE IN VARCHAR2 DEFAULT NULL,
PO_JOBID OUT NOCOPY VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_BATCHMAPCOMPID** (Mandatory). Enter COMPANY_ID of Validation Checks Batch Map.
- **PI_BATCHMAPOBJID** (Mandatory). Enter OBJ_ID of Validation Checks Batch Map.
- **PI_BATCHMAPOBJVER** (Mandatory). Enter OBJ_VER of Validation Checks Batch Map.
- **PI_CONTEXT** (Optional). Enter values as \$LIFECYCLE\$DEV, \$LIFECYCLE\$QC or \$LIFECYCLE\$PROD. If entered as null, system tries to find out the SYTEM_CONTEXT. If SYTEM_CONTEXT is not set, it defaults to \$LIFECYCLE\$DEV.
- **PI_TESTMODE** (Optional). Leave blank
- **PO_JOBID** (Optional). Installation of Validation Checks Batch submits a job. So this output parameter returns a JOB_ID for Validation Checks Batch installation.

Submit a Validation Check Batch

Use this API to submit a validation check batch.

Name

DME_PUB_VALIDATION_CHECK.submitValidationCheckBatch

Signature

```
FUNCTION SUBMITVALIDATIONCHECKBATCH
(P_API_VERSION IN VARCHAR2,
 P_INIT_MSG_LIST IN VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN
 VARCHAR2 DEFAULT CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
 CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
 X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2,
 PI_VCBATCHMODELCOMPANYID IN CDR_NAMINGS.COMPANY_ID%TYPE
 PI_VCBATCHMODELOBJID IN CDR_NAMINGS.OBJ_ID%TYPE,
 PI_VCBATCHMODELOBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE,
 PI_SUBMISSION_TYPE IN VARCHAR2 DEFAULT '$SUBMISSTYPE$IMMEDIATE',
 PI_CONTEXT IN VARCHAR2 DEFAULT '$LIFECYCLE$DEV',
 PI_SCHED_START_TS IN DATE DEFAULT NULL,
 PI_SCHED_END_TS IN DATE DEFAULT NULL,
 PI_SCHED_REPEAT_INTERVAL IN VARCHAR2 DEFAULT NULL,
 PI_SCHED_REPEAT_LIST IN VARCHAR2 DEFAULT NULL,
 PI_FORCE_EXECUTION_FLAG_RC IN VARCHAR2 DEFAULT '$YESNO$NO',
 PI_RUN_MODE_RC IN VARCHAR2,
 PI_EXECUTE_DISABLEDVC IN VARCHAR2 DEFAULT '$YESNO$NO'
) RETURN CDR_JOBS.JOB_ID%TYPE;
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_VCBATCHMODELCOMPANYID** (Mandatory). Company ID of Validation Checks Batch Model.
- **PI_VCBATCHMODELOBJID** (Mandatory). OBJ_ID of Validation Checks Batch Model.
- **PI_VCBATCHMODELOBJVER** (Mandatory). OBJ_VER of Validation Checks Batch Model.
- **PI_RUN_MODE_RC** (Mandatory). Enter '\$RUNMODES\$FULL' or '\$RUNMODES\$INCREMENT'.
- **PI_SUBMISSION_TYPE**. Enter '\$SUBMISSTYPES\$IMMEDIATE' or '\$SUBMISSTYPES\$SCHEDULED' or '\$SUBMISSTYPES\$DEFERRED'.
- **PI_CONTEXT**. Lifecycle context values like \$LIFECYCLE\$DEV, \$LIFECYCLE\$QC or \$LIFECYCLE\$PROD.
- **PI_SCHED_START_TS**. Enter start time if submission is scheduled/deferred.
- **PI_SCHED_END_TS**. Enter end time if submission is scheduled.
- **PI_SCHED_REPEAT_INTERVAL**. Enter interval time if submission is scheduled.
- **PI_SCHED_REPEAT_LIST**. Enter if submission is scheduled. Accepted values are \$SUBMISSTYPES\$HOURLY, \$SUBMISSTYPES\$DAILY, \$SUBMISSTYPES\$WEEKLY, \$SUBMISSTYPES\$MONTHLY.
- **PI_FORCE_EXECUTION_FLAG_RC**. Enter '\$YESNO\$NO' or '\$YESNO\$YES'.
- **PI_EXECUTE_DISABLEDVC**. Enter '\$YESNO\$YES' to execute disabled VCs to close discrepancies. The default value is '\$YESNO\$NO'.

This API returns the Job Id.

Check In a Validation Check Batch

Use this API to check in a validation check batch.

Name

DME_PUB_VALIDATION_CHECK.CheckinValidationCheckBatch

Signature

```
PROCEDURE CHECKINVALIDATIONCHECKBATCH
(P_API_VERSION IN NUMBER, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE,
P_VALIDATION_LEVEL IN NUMBER DEFAULT CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL,
X_RETURN_STATUS OUT NOCOPY VARCHAR2, X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT
NOCOPY VARCHAR2, PIO_NAMING IN OUT NOCOPY CDR_NAMING_VERSION_OBJ_TYPE, PI_COMMENT IN
VARCHAR2,
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory). This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Validation Checks Batch that you want to check in.

The following attributes are required:

- COMPANY_ID
- OBJ_ID
- OBJ_VER
- **PI_COMMENT** (Optional). Enter the reason you are checking in the Validation Checks Batch.

Check Out a Validation Check Batch

Use this API to check out a validation check batch.

Name

DME_PUB_VALIDATION_CHECK.CheckoutValidationCheckBatch

Signature

```
PROCEDURE checkoutValidationCheckBatch
(P_API_VERSION IN NUMBER, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PIO_NAMING IN OUT
NOCOPY CDR_NAMING_VERSION_OBJ_TYPE, PI_COMMENT IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory). This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Validation Checks Batch that you want to check in.
The following attributes are required:
 - COMPANY_ID
 - OBJ_ID
 - OBJ_VER
- **PI_COMMENT** (Optional). Enter the reason you are checking out the Validation Check Batch.

Undo Checkout For a Validation Check Batch

Use this API to undo check out for a Validation Check Batch.

Name

DME_PUB_VALIDATION_CHECK.UncheckValidationCheckBatch

Signature

```
PROCEDURE DELETEFLAG
(P_API_VERSION IN NUMBER, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
```

```
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PIO_NAMING IN OUT
NOCOPY CDR_NAMING_VERSION_OBJ_TYPE, PI_COMMENT IN VARCHAR2
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory). This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Validation Check Batch that you want to check in.
The following attributes are required:
 - COMPANY_ID
 - OBJ_ID
 - OBJ_VER
- **PI_COMMENT** (Optional). Enter the reason you are checking in the Validation Checks Batch.

Update Validation Status of a Validation Check Batch

Use this API to update validation status of a Validation Check Batch.

Name

DME_PUB_VALIDATION_CHECK.UpdateValStatus

Signature

```
PROCEDURE UPDATEVALSTATUS
( P_API_VERSION IN NUMBER, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
  CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
  X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PIO_NAMING IN
  OUT NOCOPY CDR_NAMING_VERSION_OBJ_TYPE, PI_TESTMODE IN VARCHAR2 DEFAULT NULL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_NAMING** (Mandatory). This is a parameter of table type CDR_NAMING_VERSION_OBJ_TYPE. Enter values to identify the Validation Checks Batch that you want to update validation status.
All the attributes are required.
- **PI_TESTMODE** (Optional). Leave blank.

Upgrade a Validation Check Batch

Use this API to upgrade a validation check batch.

Name

DME_PUB_VALIDATION_CHECK.UpgradeValidationCheckBatch

Signature

```
PROCEDURE UPGRADEVALIDATIONCHECKBATCH
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PI_BATCHMAPCOMPID IN
CDR_NAMINGS.COMPANY_ID%TYPE, PI_BATCHMAPOBJID IN CDR_NAMINGS.OBJ_ID%TYPE,
PI_BATCHMAPOBJVER IN CDR_NAMING_VERSIONS.OBJ_VER%TYPE
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_BATCHMAPCOMPID** (Mandatory). Enter COMPANY_ID of Validation Checks Batch Map.
- **PI_BATCHMAPOBJID** (Mandatory). Enter OBJ_ID of Validation Checks Batch Map.
- **PI_BATCHMAPOBJVER** (Mandatory). Enter OBJ_VER of Validation Checks Batch Map.

Remove Validation Check(s)

Use this API to remove validation check(s).

Name

DME_PUB_VALIDATION_CHECK.RemoveValidationChecks

Signature

```
PROCEDURE REMOVEVALIDATIONCHECKS
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PIO_VC_COLL IN OUT
NOCOPY CDR_NAMING_LIST_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PIO_VC_COLL** (Mandatory). This is a parameter of collection type CDR_NAMING_LIST_COLL that contains CDR Naming Version attributes. The attributes required for this API are:
 - COMPANY_ID
 - OBJ_ID
 - OBJ_VER

Enable or Disable Validation Checks

Use this API to enable or disable Validation Checks.

Name

DME_PUB_VALIDATION_CHECK.EnableDisableValidationChecks

Signature

```
PROCEDURE ENABLEDISABLEVALIDATIONCHECKS
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PI_VC_MAP_COLL IN
CDR_BASE_OBJ_COLL, PI_ENABLE_FLAG IN VARCHAR2,
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_VC_MAP_COLL** (Mandatory). This is a parameter of collection type CDR_BASE_OBJ_COLL that contains CDR base object attributes. The following attributes are required: COMPANY_ID, OBJ_ID, OBJ_VER for Validation Checks maps.
- **PI_ENABLE_FLAG** (Mandatory). Enter '\$YESNO\$YES' for enabling and '\$YESNO\$NO' for disabling.

Reorder Validation Checks

Use this API to re-order validation checks.

Name

DME_PUB_VALIDATION_CHECK.ReorderValidationChecks

Signature

```
PROCEDURE REORDERVALIDATIONCHECKS
(P_API_VERSION IN VARCHAR2, P_INIT_MSG_LIST IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_COMMIT IN VARCHAR2 DEFAULT
CDR_PUB_DEF_CONSTANTS.G_FALSE, P_VALIDATION_LEVEL IN NUMBER DEFAULT
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL, X_RETURN_STATUS OUT NOCOPY VARCHAR2,
X_MSG_COUNT OUT NOCOPY NUMBER, X_MSG_DATA OUT NOCOPY VARCHAR2, PI_VC_MAP_COLL IN OUT
NOCOPY DME_XFORM_MAP_COLL
);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_VC_MAP_COLL** (Mandatory). This is a parameter of collection type DME_XFORM_MAP_COLL which is a table of DME_XFORM_MAP_OBJ_TYPE type. The attributes required for this API from DME_XFORM_MAP_OBJ_TYPE are:
 - COMPANY_ID
 - OBJ_ID
 - OBJ_VER
 - EXECUTION_ORDER_NUMBER

Data Loads

This chapter contains the following section:

- [Submit Clinical One Data load](#)

Submit Clinical One Data load

Use this API to invoke a data load from Clinical One on demand.

Name

DME_PUB_DF_DATA_MODEL.StartC1DataLoad

Signature

```
PROCEDURE StartC1DataLoad(p_api_version      IN NUMBER
                          ,p_init_msg_list   IN VARCHAR2 default
CDR_PUB_DEF_CONSTANTS.G_FALSE
                          ,p_commit         IN VARCHAR2 default
CDR_PUB_DEF_CONSTANTS.G_FALSE
                          ,p_validation_level IN NUMBER      default
CDR_PUB_DEF_CONSTANTS.G_VALID_LEVEL_FULL
                          ,x_return_status  OUT NOCOPY   VARCHAR2
                          ,x_msg_count      OUT NOCOPY   NUMBER
                          ,x_msg_data       OUT NOCOPY   VARCHAR2
                          ,pi_study_id       IN CDR_NAMINGS.OBJ_ID%TYPE
                          ,pi_context       IN VARCHAR2
                          ,pi_run_mode      IN VARCHAR2 default
'$RUNMODES$INCREMENTAL'
                          ,x_job_id         OUT NOCOPY   NUMBER);
```

Parameters

This API has standard parameters (see [Standard Parameters](#)) and the following parameters:

- **PI_STUDY_ID** (Mandatory). Enter STUDY_ID of Clinical One Data Model.
- **PI_CONTEXT** (Mandatory). Enter Lifecycle context values like \$LIFECYCLE\$DEV, \$LIFECYCLE\$QC or \$LIFECYCLE\$PROD.
- **PI_RUN_MODE**. Enter '\$RUNMODES\$FULL' or '\$RUNMODES\$INCREMENTAL'.
- **X_JOB_ID**. On calling this procedure, it submits a job. So this output parameter returns a job ID of successfully submitted job.

This API returns the Job ID.

Part V

Public Views

Part V contains the following chapter:

- [Public Views](#)

Public Views

Public views fetch data only if the sys_context setting is enabled by an Oracle DMW login through the API. Public views do not have explicit object-level security checking.

This section includes the public views for the following APIs:

- [Clinical Data Model Views](#)
- [Codelist Views](#)
- [Discrepancy Views](#)
- [Validation Checks Views](#)
- [Transformation Views](#)
- [Thesaurus Management System-Related Views](#)
- [Generic Business Area Views](#)
- [Security-Related Views](#)
- [Snapshot Label View](#)

Clinical Data Model Views

This section contains public views related to clinical data models.

- [DME_PUB_DATAMODEL_V](#)
- [DME_PUB_TABLES_V](#)
- [DME_PUB_COLUMNS_V](#)
- [DME_PUB_CONSTRAINT_V](#)
- [DME_PUB_CONSTRAINT_COLS_V](#)
- [DME_PUB_LOV_VALUES_V](#)
- [DME_PUB_COL_DISP_CHARS_V](#)
- [DME_PUB_SDTM_COL_IDENTIFIERS_V](#)
- [DME_PUB_SDTM_TAB_IDENTIFIERS_V](#)

DME_PUB_DATAMODEL_V

Use this view to see study and library clinical data model definitional details.

DME_PUB_TABLES_V

Use this view to see clinical data model table definitional details.

DME_PUB_COLUMNS_V

Use this view to see clinical data model table column definitional details.

DME_PUB_CONSTRAINT_V

Use this view to see clinical data model table constraint definitional details.

DME_PUB_CONSTRAINT_COLS_V

Use this view to see clinical data model table constraint column definitional details.

DME_PUB_LOV_VALUES_V

Use this view to see clinical data model table check constraint lists of values.

DME_PUB_COL_DISP_CHARS_V

Public view with details needed to invoke the Modify Column Display Characters API.

DME_PUB_SDTM_COL_IDENTIFIERS_V

Use this view to see SDTM column identifier definitional details.

DME_PUB_SDTM_TAB_IDENTIFIERS_V

Use this view to see SDTM table identifier definitional details.

Codelist Views

This section contains public views related to codelists.

- [DME_PUB_CODELIST_V](#)
- [DME_PUB_CODELIST_VALUES_V](#)
- [DME_PUB_XFM_FILTER_VALUES_V](#)

DME_PUB_CODELIST_V

Use this view to see codelist definitional details.

DME_PUB_CODELIST_VALUES_V

Use this view to see codelists with their values.

DME_PUB_XFM_FILTER_VALUES_V

Use this view to see the codelist codes and values associated with a column in a DMW table that is used as a pivot column in a transformation.

Discrepancy Views

This section contains public views related to discrepancies.

- [DME_PUB_DISCREPANCIES_V](#)
- [DME_PUB_DISC_SEND_ERRORS_V](#)

DME_PUB_DISCREPANCIES_V

Use this view to see discrepancy details, including the study, clinical data model, table, and column against whose data the discrepancy was raised.

DME_PUB_DISC_SEND_ERRORS_V

Use this view to help figure out why new or updated discrepancies created by validation checks or TMS that should be sent to InForm (or another integrated EDC system) failed to be sent. It contains a row for each Send failure.

Validation Checks Views

This section contains public views related to validation checks.

- [DME_PUB_VC_BATCHES_V](#)
- [DME_PUB_VC_DETAILS_V](#)

DME_PUB_VC_BATCHES_V

Use this view to see validation check batch definitional details. The following query returns the validation check batches that read from a given clinical data model:

```
Select * from DME_PUB_VC_BATCHES_V
where SRC_MODEL_COMPANY_ID = <company_id> and
SRC_MODEL_OBJ_ID = <obj> and
SRC_MODEL_OBJ_VER = <ver>;
```

The following parameters are required for operations related to a batch; for example, update, check in, uncheck, check out, install, and so on.

```
BATCH_MAP_COMPANY_ID
BATCH_MAP_OBJ_ID
BATCH_MAP_OBJ_VER
BATCH_MAP_NS_OBJ_ID
BATCH_MAP_NS_OBJ_VER
BATCH_MAP_OBJECT_VER_NUM
```

DME_PUB_VC_DETAILS_V

Use this view to see validation check details. The following query returns the validation checks available for a given validation check batch.

```
Select * from DME_PUB_VC_DETAILS_V
where vc_company_id= <vc_batch_map_company_id>
and VC_BATCH_MAP_OBJ_ID = <vc_batch_map_id>
```

```
and <vc_batch_map_version>  
between VC_MAP_NS_START_OBJ_VER and VC_MAP_NS_END_OBJ_VER;
```

Transformation Views

This section contains public views related to transformations.

- [DME_PUB_DF_XFORM_MAP_V](#)
- [DME_PUB_DF_MAP_ENTITY_V](#)
- [DME_XFM_FILTER_VALUES_V](#)
- [DME_PUB_XFM_SOURCE_TABLES_V](#)
- [DME_PUB_XFM_SOURCE_COLUMNS_V](#)
- [DME_PUB_XFM_TARGET_TABLES_V](#)
- [DME_PUB_XFM_TARGET_COLUMNS_V](#)
- [DME_PUB_XFM_AUTOMAPS_V](#)
- [DME_PUB_XFM_COL_AUTOMAPS_V](#)
- [DME_PUB_XFM_CUSTOM_PROGRAMS_V](#)
- [DME_PUB_XFM_EXPR_STDFUNC_V](#)
- [DME_PUB_XFM_EXPR_STATIC_PKGS_V](#)

DME_PUB_DF_XFORM_MAP_V

Use this view to see transformation map details.

DME_PUB_DF_MAP_ENTITY_V

Use this view to see map entity details.

DME_XFM_FILTER_VALUES_V

Use this view to see the codelist codes and values associated with a column in a DMW table that is used as a pivot column in a transformation.

DME_PUB_XFM_SOURCE_TABLES_V

Use this view to see source database tables involved in table mappings.

DME_PUB_XFM_SOURCE_COLUMNS_V

Use this view to see details of columns from the source database tables, which are mapped to columns in target database table.

DME_PUB_XFM_TARGET_TABLES_V

Use this view to see details for target database tables involved in table mappings.

DME_PUB_XFM_TARGET_COLUMNS_V

Use this view to see details of the columns from the target database tables, to which one or more source table are mapped.

DME_PUB_XFM_AUTOMAPS_V

Use this view to see details of the available auto maps at table level.

DME_PUB_XFM_COL_AUTOMAPS_V

Use this view to see details of available auto maps at column level.

DME_PUB_XFM_CUSTOM_PROGRAMS_V

Use this view to see the details of the available custom programs.

DME_PUB_XFM_EXPR_STDFUNC_V

Use this view to see supported standard Oracle Scalar functions and their respective function return types. You can refer to these functions while creating the expressions.

DME_PUB_XFM_EXPR_STATIC_PKGS_V

Use this view to see the user defined LSH stored functions Scalar functions and their respective details. You can check available user-defined functions from this view and can use these functions while dealing with expressions.

Thesaurus Management System-Related Views

This section contains public views related to TMS integration with Oracle DMW.

- [DME_PUB_TMS_STUDY_DOM_ELEMS_V](#)
- [DME_PUB_TMS_SETS_V](#)
- [DME_PUB_TMS_SET_COLS_V](#)

DME_PUB_TMS_STUDY_DOM_ELEMS_V

Use this view to see TMS domains and the studies they are assigned to in DMW.

DME_PUB_TMS_SETS_V

Use this view to see TMS Sets created to derive data from TMS to DMW.

DME_PUB_TMS_SET_COLS_V

Use this view to see TMS Set columns and the information they derive from TMS to the DMW table columns they are mapped to.

Generic Business Area Views

This section contains public views related to generic business areas (for data visualizations).

- [CDR_PUB_GENERIC_BA_V](#)
- [CDR_PUB_GENERIC_BA_TABLES_V](#)

CDR_PUB_GENERIC_BA_V

Use this naming view to retrieve all the Generic Visualization Business Area Instances on which a user has privileges to read data.

CDR_PUB_GENERIC_BA_TABLES_V

Use this view to retrieve the Table instance details for a given GV BAI.

Security-Related Views

This section contains public views related to security.

- [CDR_PUB_UG_ROLES_V](#)
- [CDR_PUB_USER_UG_ROLES_V](#)
- [CDR_PUB_SUBTYPE_OPR_ROLES_V](#)
- [CDR_PUB_OBJ_UG_V](#)

CDR_PUB_UG_ROLES_V

Use this view to see roles assigned to user groups.

CDR_PUB_USER_UG_ROLES_V

Use this view to see users assigned to roles in user groups.

CDR_PUB_SUBTYPE_OPR_ROLES_V

Use this view to see operations on object subtypes assigned to roles.

CDR_PUB_OBJ_UG_V

Use this view to see user group assignments to objects.

Snapshot Label View

This section contains a public views related to snapshot labels.

- [CDR_PUB_SNAPSHOT_LABEL_V](#)

CDR_PUB_SNAPSHOT_LABEL_V

Use this view to see snapshot labels and the tables they are assigned to.