# Oracle® Retail AI Foundation Cloud Services Assortment and Space Optimization User Guide





Oracle Retail Al Foundation Cloud Services Assortment and Space Optimization User Guide, Release 25.2.301.0

G39078-01

Copyright © 2025, Oracle and/or its affiliates.

Primary Author: Judith Meskill

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software, software documentation, data (as defined in the Federal Acquisition Regulation), or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software," "commercial computer software documentation," or "limited rights data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed, or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle®, Java, MySQL, and NetSuite are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

# Contents

1

### Send Us Your Comments

Preface	
Audience	i
Documentation Accessibility	i
Related Documents	i
Customer Support	i
Improved Process for Oracle Retail AI Foundation Cloud Services Documentation Corrections	ii
Oracle Retail Al Foundation Cloud Services Documentation on the Oracle Help Center	ii
Conventions	ii
Assortment and Space Optimization	
Overview	1
Administering ASO	1
Users and Roles	1
Overview of the User Interface	4
Icons	5
Buttons	6
Pull-Down Menus	7
Histograms	8
Charts	8
Process Train	8
Embedded Help	8
Process Indicator	8
Search	8
Workflow	8
Optimization	9
Space Cluster	9
Run Templates	9
Validation	10
Planogram Mappings	10

Smart Start Process	10
Fixture Types	10
Virtual Planogram	10
Planogram Set	11
Assortment Finalization	11
Assortment List	11
Assortment List	11
About Rollbacks	13
Assortment Analysis	13
Optimization List	17
Optimization List Interface	18
Create a Run	19
Copy a Run	19
Open a Run	19
Delete a Run	19
Execute Space Optimization	20
Optimization Setup	20
Summary	20
Setup	21
Review Optimization Locations	24
Contextual Information	27
Fixture and Product Data	29
Summary	29
Planogram Fixtures	30
Product Merchandise Data	39
Demand and Replenishment Data	44
Objective and Constraints	48
Summary	48
Objectives and Constraints Summary	48
Select Locations and Products	50
Objectives and Constraints Details	51
Contextual Information	66
Results and Analysis	66
Optimization Results	67
Included Products	68
Dropped Products	68
Alerts	69
Contextual Information	70
Planograms	70
Validation	75
Details About Errors and Warnings	76
Warnings	76

Correcting Errors	80
Assortment Mapping	81
Assortment Mapping Interface	81
Select Assortment	81
Assortment to Planogram Mapping	82
Mapping Errors	84
ASO Integration with Assortment Planning	84
ASO Integration	85

# Appendix: Oracle Retail AI Foundation Cloud Services Overview



# Send Us Your Comments

Oracle Retail AI Foundation Cloud Services Assortment and Space Optimization User Guide

Oracle welcomes customers' comments and suggestions on the quality and usefulness of this document.

Your feedback is important, and helps us to best meet your needs as a user of our products. For example:

- Are the implementation steps correct and complete?
- Did you understand the context of the procedures?
- Did you find any errors in the information?
- Does the structure of the information help you with your tasks?
- Do you need different information or graphics? If so, where, and in what format?
- Are the examples correct? Do you need more examples?

If you find any errors or have any other suggestions for improvement, then please tell us your name, the name of the company who has licensed our products, the title and part number of the documentation and the chapter, section, and page number (if available).



#### (i) Note

Before sending us your comments, you might like to check that you have the latest version of the document and if any concerns are already addressed. To do this, access the Online Documentation available on the Oracle Help Center It contains the most current Documentation Library plus all documents revised or released recently.

Send your comments to us using the electronic mail address: retail-doc\_us@oracle.com

Please give your name, address, electronic mail address, and telephone number (optional).

If you need assistance with Oracle software, then please contact your support representative or Oracle Support Services.

If you require training or instruction in using Oracle software, then please contact your Oracle local office and inquire about our Oracle University offerings. A list of Oracle offices is available on our Web site at http://www.oracle.com.



# **Preface**

This guide describes the Oracle Retail AI Foundation Cloud Services Assortment and Space Optimization user interface. It provides step-by-step instructions to complete most tasks that can be performed through the application.

# **Audience**

This User Guide is intended for retailers and analysts.

# **Documentation Accessibility**

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <a href="http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc">http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc</a>.

#### **Access to Oracle Support**

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <a href="http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info">http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info</a> or visit <a href="http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs">http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs</a> if you are hearing impaired.

### **Related Documents**

For more information, see the following documents in the Oracle Retail AI Foundation Cloud Services documentation set:

- Oracle Retail AI Foundation Cloud Services Administration Guide
- Oracle Retail AI Foundation Cloud Services Implementation Guide
- Oracle Retail AI Foundation Cloud Services Security Guide
- Oracle Retail AI Foundation Cloud Services Release Notes
- Oracle Retail Analytics and Planning Cloud Services Data Interface
- Oracle Retail AI Foundation Cloud Services User Guide
- Oracle Retail AI Foundation Cloud Services Assortment and Space Optimization User Guide
- Oracle Retail Inventory Planning Optimization Cloud Service-Inventory Optimization User Guide
- Oracle Retail Lifecycle Pricing Optimization Cloud Service User Guide

# **Customer Support**

To contact Oracle Customer Support, access My Oracle Support at the following URL:



#### https://support.oracle.com

When contacting Customer Support, please provide the following:

- Product version and program/module name
- Functional and technical description of the problem (include business impact)
- Detailed step-by-step instructions to re-create
- Exact error message received
- Screen shots of each step you take

# Improved Process for Oracle Retail AI Foundation Cloud Services Documentation Corrections

To more quickly address critical corrections to Oracle Retail AI Foundation Cloud Services documentation content, Oracle Retail AI Foundation Cloud Services documentation may be republished whenever a critical correction is needed. For critical corrections, the republication of an Oracle Retail AI Foundation Cloud Services document may at times not be attached to a numbered software release; instead, the Oracle Retail AI Foundation Cloud Services document will simply be replaced on the Oracle Help Center Web site, or, in the case of Data Models, to the applicable My Oracle Support Documentation container where they reside.

Oracle Retail AI Foundation Cloud Services documentation is available on the Oracle Help Center at the following URL:

#### https://docs.oracle.com/en/industries/retail/index.html

An updated version of the applicable Oracle Retail AI Foundation Cloud Services document is indicated by Oracle part number, as well as print date (month and year). An updated version uses the same part number, with a higher-numbered suffix. For example, part number E123456-02 is an updated version of a document with part number E123456-01.

If a more recent version of a document is available, that version supersedes all previous versions.

# Oracle Retail AI Foundation Cloud Services Documentation on the Oracle Help Center

Oracle Retail AI Foundation Cloud Services product documentation is available on the following web site:

#### https://docs.oracle.com/en/industries/retail/index.html

(Data Model documents are not available through Oracle Help Center. You can obtain these documents through My Oracle Support.)

## Conventions

The following text conventions are used in this document:



Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
italic	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

# **Assortment and Space Optimization**

Oracle AI Foundation Assortment and Space Optimization Cloud Service is used to determine the optimal selection and arrangement of products within stores by optimizing the product assortment and product placement on a virtual planogram. It uses information about available space, product dimensions, expected demand, replenishment schedules, merchandising rules, fixture space, and category goals in order to create a virtual planogram that optimizes total performance.

The products and product assortments that are selected for the virtual planograms are the ones that ASO Cloud Service recommends for the finalized assortment. The recommended product level data is used inside CMPO, while the virtual planograms created in ASO Cloud Service are also then available to be used in space planning.

It supports the following fixture types:

- Shelves
- Pegboards
- Freezer chests
- Shelf/pegboard combinations

Optimizations are run at either the Store level or at the Space Cluster level. Space Clusters are ad hoc groups of stores used for optimization. Each space cluster includes stores that are in the same assortment, have the same product list, and have the same current planogram length (or same POG length, height, and depth, if selected). Space clusters are typically a level between assortment cluster and store. ASO Cloud Service creates these groups by splitting stores from an assortment cluster into smaller groups of stores that have the same product list and the same current planogram length.

At a high level, ASO Cloud Service starts with an assortment that is ready for optimization. The assortment is mapped to one or more planograms, and one or more optimization runs occur. Approved runs are then available for assortment analysis and can then be finalized and exported.

## **Overview**

This section provides information to help you understand the functionality of ASO.

# Administering ASO

For information about the administration of ASO Cloud Service, see *Oracle Retail Al Foundation Cloud Services Administration Guide*.

### **Users and Roles**

The following four user login roles are available:

 Micro Space Optimization Analyst – main business user responsible for day-to-day microspace optimization activities



- Category Manager product-assortment-centric user who is interested in viewing ASO results and in the translation of data between CMPO, Retail Analytics, and ASO
- Administrator responsible for general system setup and configuration tasks related to the business
- Analytical Super User responsible for analytical configuration, testing, and model diagnosis

Table 1-1 User Roles and Permissions

Privilege	Data Access	Micro ASO Analyst	Category Manager	Administrator	Analytical Super User
Create new ASO run	All runs	X			X
Modify existing ASO run	Runs they created	X			Χ
Modify the name and description of an existing ASO run.	Runs they created	X			X
View existing ASO run	All runs	X	Χ	X	X
Submit or re- submit ASO run	Runs they created	X			X
	Runs they created with technical failures	X			X
Approve ASO runs	Runs they created	X			
Delete saved ASO runs	Runs they created	X			Χ
	All runs			X	
View list of saved ASO runs	All runs	X	X	X	Χ
View mapping of products to POG sets	All assortments	X	X	X	X
Modify mapping of products to POG sets	All assortments		X		X
Toggle assortment status between Ready for ASO and POG Mapping Needs Review	All assortments		X		X
View rules for mapping products in POG sets	All assortments	X	X	X	X
Modify rules for mapping products to POG sets	All assortments		X		X



Table 1-1 (Cont.) User Roles and Permissions

Privilege	Data Access	Micro ASO Analyst	Category Manager	Administrator	Analytical Super User
Analyze space- optimized assortments	All assortments	X	X	X	X
Finalize and export space-optimized assortments	All assortments		X		
Roll back finalized and exported space-optimized assortments	All assortments			X	
View list of space- optimized assortments	All assortments	X	X	X	X
Delete unprocessed assortment	All assortments			X	

**Table 1-2 User Constraints** 

Role		Privilege		Object	Status
Users	Cannot	Modify existing ASO run	When	Run is	Running, approved, or finalized
Users	Cannot	Submit or resubmit ASO runs	When	Run is	Running, approved, or finalized
Users	Cannot	Approve ASO runs	Unless	Run is	Complete
Users	Cannot	Delete saved ASO runs	When	Run is	Running, approved, or finalized
Administrator	Cannot	Delete saved ASO runs	When	Run is	Finalized
Users	Cannot	Modify mapping of products in POG sets	Unless	Assortment is	With status of POG Mapping Needs Review
Users	Cannot	Toggle assortment status between Ready for ASO and POG Mapping Needs Review	When	Assortment is	With status of POG Mapping Needs Review and also has mappings with errors (both conditions must be true)
Users	Cannot	Modify rules for mapping products to POG sets	When	Assortment is	Finalized or exported

**Table 1-3 Privilege Descriptions** 

Privilege	Description
Create new ASO run	Set up and execute optimizations. All steps on the main train can be carried out, including creating a new run via the copy run or the save as functionality.



Table 1-3 (Cont.) Privilege Descriptions

Privilege	Description
Modify existing ASO run	Open an existing run and modify settings. The user can visit and change settings on any step in the main train. This includes performing VPOG overrides for the optimal VPOGs that are generated by the run.
Modify the name and description of an existing ASO run	Open an existing run and modify the name and description of that run.
View existing ASO run	Open an existing run and visit any step in the main train. The user can view data and search/aggregate/filter but cannot change anything. This includes viewing the optimal VPOGs that are generated by the run and comparing them to historical VPOGs.
Submit or re-submit ASO run	Submit a new or modified run or restart a failed run. This includes validating a run.
Approve ASO runs	Approve run results.
Delete saved runs	Delete run setup information and results from the database.
View list of saved runs	View a list of summary details about each saved run.
View mapping of products to POG sets	View the mapping of products to POG sets by assortment.
Modify mapping of products to POG sets	Modify the mapping and related data of products to POG sets by assortment. This includes altering the mappings by using the re-map functionality, which refreshes an assortment's mappings based on the pre-configured rules.
Toggle assortment status between Ready for ASO and POG mapping needs review	Toggle an assortment's status between Ready for ASO and POG mapping needs review.
View rules for mapping products to POG sets	View the rules that determine how products are mapped to POG sets.
Modify rules for mapping products to POG sets	Edit the rules that determine how products are mapped to POG sets.
Analyze space optimized assortments	Aggregate approved runs to the assortment level prior to approval for export to CMPO.
Finalize and export space optimized assortments	Finalize assortments and export the aggregated assortment data to export to CMPO.
Rollback finalized and exported space optimized assortments	Roll back a finalized assortment or an exported assortment.
View list of space optimized assortments	View a list of summary details about each of the space-optimized assortments.
Delete unprocessed assortment	Delete assortments that have not moved into ASO processing. Only assortments that have the following statuses can be deleted: Received, Data Errors, Ready for Mapping, Discarded, and POG Mapping Needs Review.

# Overview of the User Interface

The ASO Cloud Service user interface, at a high level, consists of:

 Task pane. Located on the left side of the application. Use this to navigate between the four main tabs.



- The four tabs that you use to do the application work: Optimization List, Assortment List, Execute Space Optimization, and Assortment Mapping.
- Contextual information. Located on the right side of the application. Use the various tabs to set up runs and to view graphical and tabular data that can help you as you interpret the optimization results. In addition, the tools can be used during the run setup to provide additional information about data involved in the run setup.

#### **Icons**

The following icons are used in user interface. Certain icons have slightly different definitions, depending on the context.

Table 1-4 Icons

Icon	Icon Description
+	Add. Add row.
***	Compare to history.
	Copy a run. Add a planogram. On the Assortment Mappings screen, it is used to create a like planogram.
•	Create. Create a run.
	Detach.
×	Delete. Delete a run. Delete planogram.
1	Edit. Change status.
?	Embedded help.
<b>3</b>	Export to Excel. Export all.
	Freeze.
恒	Go to top.
<b>=</b>	Go up.
<b>&gt;&gt;&gt;</b>	Move all items to other list.
>	Move selected items to other list.
0	Progress indicator. The indicator changes mode when the application is processing data.
最	Query by example.



Table 1-4 (Cont.) Icons

Icon	Icon Description
9-9	Re-map.
<u>@</u>	Refresh.
<b>«</b>	Remove all items from list.
3	Remove selected items from list.
*	Required.
126	Select date.
22	Show as top.
66	View configuration. View results.
4	Wrap.

# **Buttons**

Buttons are used to perform certain actions and for navigation.

Table 1-5 Buttons

Button	Button Description
Action	Provides access to the following actions: Submit, Re-Submit, Validate, Save As, and Approve.
Add All Stores	Within the Add Stores dialog box, used to add all stores instead of a sub-group of stores.
Apply	In Optimization Objectives, used with the Edit Objectives drop-down list.
Back	Used to return to the previous train stop.
Cancel	Used to close a dialog box without making a selection.
Choose Stores	In Optimization Setup, when creating a new run, provides access to a dialog box for adding stores.
Clear Selection	In Assortment Analysis, clears the Selected Runs list.
Details	Radio button that toggles the display between a detailed view and a summary view.
Edit Constraints	In Optimization Objectives, provides access to the Edit Constraints dialog box, which you use to edit settings.
Export	In Assortment Analysis, makes the selected finalized run available for use by other applications.
Finalize	In Assortment Analysis, finalizes the selected run.
Next	Moves to the next train stop.



Table 1-5 (Cont.) Buttons

Button	Button Description
No Template	Clears the template section.
Save	Saves the existing settings.
Summary	Radio button that toggles the display between a detailed view and a summary view.
Table View	Radio button that toggles the display between a table view of the data and a tree view of the data.
Tree View	Radio button that toggles the display between a table view of the data and a tree view of the data.
View Results	In Assortment Analysis, displays results for runs in the Selected Runs list.

#### **Pull-Down Menus**

The user interface has three pull-down menus that provide access to a variety of functionality.

The **Format** pull-down menu and the **View** pull-down menu can be used to adjust how the display is organized. For example, you can resize the columns or detach a table from the interface.

The **Actions** pull-down menu provide functionality that you use to manipulate the application data. Some of the following functionality is also provided by the icons described in Table 1-4.

Table 1-6 Actions Pull-Down Menu Functionality

Action Name	Description
Create Run	In Optimization List, takes user to Optimization Setup train stop.
Copy Run	In Optimization List, used to create a duplicate of an existing run.
Delete Run	In Optimization List, used to delete a run.
Export to Excel	Used to export to Excel.
Rollback	In Assortment List, used to revert the status of a run.
Re-Мар	In Assortment Mapping, re-maps the planogram to product. This action must be executed after adding POGs, mapping data or any other information that has been delivered in order to correct exceptions or errors found by the assortment to POG mapping process.
Add Planogram	In Assortment Mapping, provides access to the Select Planogram Nodes dialog box.
Delete Planogram	In Assortment Mapping, used to delete the selected planogram.
Add Row	Add a row to the display.
Mark for Optimization	In Fixture and Product Data, used to select a product for optimization (indicated with a check mark).
View Configuration	In Fixture and Product Data, displays an empty planogram for the selected product.
Compare to History	In Fixture and Product Data, and in Results and Analysis, displays historical planogram that is populated.
Add	In Objectives and Constraints - Product Groups, used to add data.
Edit	In Objectives and Constraints - Product Groups, used to edit data.
Delete	In Objectives and Constraints - Product Groups, used to delete data.



Table 1-6 (Cont.) Actions Pull-Down Menu Functionality

Action Name	Description
View Results	In Assortment Analysis, processes the selected run. Once the processing is complete, the results are displayed in the table.
Export All	In Results and Analysis, used to export all the results.
Create	In Fixture and Product Data, used to create.
Change Status	In Assortment Mapping, used to update the status.
Save As	Makes a copy of the run that is currently open.

### Histograms

The stages have associated histograms available on the right-hand side of the display that can help you analyze the data presented in that stage. You can adjust the way the histogram presents the data by changing the number of bins that are used in the display. Once you change the number of bins, click the **Refresh** button to update the display.

#### Charts

Certain stages have associated charts available on the right-hand side of the display that list data in a tabular format.

#### **Process Train**

The process train displays the stages of Execute Space Optimization. The current stage is highlighted. You can also use the **Back** button and the **Next** button to move through the train.

### **Embedded Help**

Embedded help, which you access by clicking the **Question Mark** icon, provides additional information about the details required by certain fields.

### **Process Indicator**

At the top of the user interface, in the right-hand corner, is a process indicator that you can use to monitor the status of a user action such as clicking **Next** to go to the next stage.

### Search

In certain cases, you can customize your search, using advanced search capabilities to specify the search criteria.

### Workflow

ASO Cloud Service is used to optimize a category manager's assortment plan by creating optimal planograms. The category manager creates a preliminary assortment and wants to determine how well that list of products can fit in stores, given the available space, product sizes, and merchandising goals, constraints, and rules. The application creates virtual planograms that organize products onto fixtures in a way that best achieves the optimization objectives. Once the manager finalizes the optimization results, the product level data can be exported for use in planning applications.



# Optimization

An optimization can be carried out at one of two location levels: Store or Space Cluster.

In a Store level optimization:

- each store is optimized separately, based on the store's individual data
- one planogram is produced for each store
- store-specific results are produced

In a Space Cluster level optimization:

- every space cluster is optimized separately, based on aggregate store data
- one planogram is produced for each space cluster
- space-cluster-specific results are produced

# **Space Cluster**

A space cluster is an ad hoc group of stores used for optimization. Each space cluster includes stores that are in the same assortment, have the same product list, and have the same current planogram length. Space clusters are typically a level between assortment cluster and store. A fixture configuration can optionally be added to the clustering rules. ASO Cloud Service creates these groups by splitting stores from an assortment cluster into smaller groups of stores that have the same product list, the same current planogram length, and same fixture configuration if activated.

# Run Templates

You can pick an existing run that was created for the same POG Set as a template. The system uses the settings for that run and applies them to a new run (which has a new group of products, locations, and data). This allows you to leverage the initial settings from the template run and use them across time, locations, planogram sets, and users. These templates work as follows:

- Product Groups. ASO copies whatever is saved at the top level from the template run to destination run.
- Objective Function and POG constraints. Most of the common values from the template are applied to all bottom levels in the new run. This includes the run objective, blocking constraint, spacing constraint, merge bay constraint, usable space constraint, and service level.
- Product merchandising rules are copied as is from the template run to the destination run.
   This includes the fixture type, display style, orientation, capping, stacking/capping style, and max stack.
- For visual guidelines, product family group, and sort order. the All Locations visual
  guidelines for each fixture type are copied to the destination run. For Product Family Group
  and Sort Order, the All Locations Product Family Group and Sort Order are copied to the
  destination run.
- If the template run is set up at the space cluster-level and the destination run is set up at store level, then most common values will be taken from all lower levels as well whatever is defined at the top level (All Locations) that is applicable to the new run.



 The user can select any run as a template; however, picking an unrelated run (a different POG set or assortment) will only transfer values that use the most common values. Most common values are not specific to any POG set or assortment; they are simply global values taken from the template run. In the template process, ASO discards any product/ store level settings that exist only within template but are not valid for the destination run.

### Validation

Within each stage, you can perform a validation. This provides you with feedback concerning the settings you have configured. Validation can identify conflicts between settings. You see details in the validation report that can help you to resolve any issues. Note that the validation is the same, regardless of which stage you invoke it from.

The conflicts identified by validation include warnings and errors. Warnings occur when constraints can impact or limit the optimization process. Errors prevent the optimization process from producing a solution.

# Planogram Mappings

ASO Cloud Service supports various planogram mappings, including the simple case in which a single product category is mapped to a single planogram as well as the case in which a product category's assortment is mapped to multiple planograms in many locations in a store.

### **Smart Start Process**

If detailed shelving data is not available, a planogram cannot show the complete details about the shelving. In such cases, ASO Cloud Service creates fixture details using a combination of default values and user selection in order to assign shelves to partial shelf fixture planograms. This process occurs automatically when optimization locations are generated. These fixture configurations are available in the Fixture and Product Data stage. The user can manually override such planograms within the ASO Cloud Service user interface. See <u>Planogram Setup</u> for additional information.

# Fixture Types

ASO Cloud Service works with three types of fixtures: shelves, pegboards, and freezer chests. Freezer chests are not the containers in the frozen food section; rather, they are chests that shoppers reach down into in order to select a product. Planograms can support a mixture of shelves and pegboards.

# Virtual Planogram

A virtual planogram (VPOG) is a planogram that is created by the application. It contains colored rectangles representing products, product groups, or images of products (when available), with supporting hover text for each product on the virtual planogram. A planogram is the layout of the product on shelves or pegboards with an underlying fixture assumption (for example, the number of shelves or the overall size).

A user can open multiple virtual planograms simultaneously in order to view images for different clusters or stores within the same run. However, only the first virtual planogram that a user opens can be edited, subject to the run status and the permission rules, until the open virtual planograms are closed. The application only supports the opening of multiple simultaneous virtual planograms if the user is using the same browser session, browser tab, and login session for the same optimization run. In other words, the user must open the multiple virtual planograms for a single run in a single run screen. All other combinations of



browser sessions, browser tabs, and multiple logins to open multiple simultaneous virtual planogram windows are not supported. Although some combinations may work in practice, consistent UI behavior is not guaranteed and data integrity issues may occur.

# Planogram Set

Planogram set is an ASO concept that refers to a planogram node (which is the subcategory name) and concatenates it with the planogram season, with a hyphen between.

### Assortment Finalization

The Assortment Finalization process handles the assortment summarization of the results at the assortment set level as well as the transformation of placeholder product names and IDs into final products. This process is initiated by the Assortment Planning and Optimization (APO) module of CMPO. ASO loads and integrates the Assortment Finalization file with database objects. This triggers the following:

- ASO generates aggregated results for all the exported assortments that have the same assortment set ID.
- The only assortments that are aggregated are the ones that have been exported to APO.
- All other assortments that have the same assortment set ID but that have a status other than exported are disabled so they can no longer be used in optimization or analysis.

## **Assortment List**


The Assortment List tab has one table that presents a list of all available assortments. You can use this information to view descriptive information and the status of each of the listed assortments. Use the **Refresh** icon to update the display.

You can also access the Assortment Analysis functionality from the Assortment List tab. You use the Assortment Analysis screen to determine how much of an assortment has or has not been optimized, to analyze the results of the optimizations, and to finalize and export your work.

## **Assortment List**

The Assortment List is shown in Figure 1-1.

Figure 1-1 Assortment List





It contains the following columns.

**Table 1-7** Assortment List

Field	Description
Name	The display name for the assortment.
Goal	The goal of the assortment.
Role	The role of the assortment.
Tactic	The tactic of the assortment.
Received On	The date the assortment was received.
Last Updated By	The user ID of the person who most recently updated the assortment.
Last Update	The date when the assortment was most recently updated.
Location Level	The location level for the assortment (Cluster Assortment, Store Assortment, or Space Cluster). This is the level at which the assortment data is delivered. Products are delivered once for all stores within a cluster (Cluster Assortment) or once for every store (Store Assortment)
Status	The status of the assortment in terms of space optimization. Values include Received, Data Errors, Ready for Mapping. POG Mapping Needs Review, User Re-Mapping, Ready for SO, Finalized, Exported, and Assortment Set Finalized. See <a href="Table 1-8">Table 1-8</a> for details about each status.
	Select any assortment with a status of Finalized or Ready for SO in order to display that assortment in Assortment Analysis.
Run Count	The total number of existing optimization runs (regardless of status) that have occurred, based on a planogram set that is included in the assortment.
Trading Area	The trading area for the assortment.
Product Category	The product category for the assortment.

**Table 1-8 Assortment Status Descriptions** 

Status	Description
Received	The assortment has been received by ASO and has been loaded within ASO tables.
Data Errors	The assortment has been validated by ASO against other datasets in the application, and errors have been found. Assortments that have failed global validation checks will have a change of status to Data Errors and will not be included in any further processing until the data is fixed and a new global validation run verifies the data integrity.
Ready for Mapping	The assortment has passed global validation so its status has changed to Ready for Mapping. As a result, the assortment can now be included in the Assortment to POG mapping process.
POG Mapping Needs Review	The mapping process has been executed and some exceptions have been found that require user review. Depending on the system configuration, a review might be required, regardless of mapping process results.
User Re-Mapping	Internal state is not visible in UI. This is an internal indicator for a new mapping request from the user.
Ready for SO	The assortment has been mapped. It is exception free and available for use within the optimization process.



Table 1-8 (Cont.) Assortment Status Descriptions

Status	Description
Finalized	An individual assortment reaches this status once the assortment's results have been reviewed and accepted by the user.
Exported	The final status of the individual assortment, indicating that the data is available for export.
Assortment Set Finalized	This is a signal from APO indicating that the processing for the whole assortment has ended and that the combined results from the related assortments in SET should be created and made available for export.

#### About Rollbacks

The **Rollback** functionality is available from the **Action** drop-down menu.

If the current status of the assortment is Exported, the status rolls back to Finalized. After the rollback from Exported, the assortment is not available to external application (as it was when it had a status of Exported).

You cannot roll back any run. If an assortment is in Finalized status, you will not be able to create any new runs based on POG sets within that assortment so you must roll the assortment back to Ready for SO status, create more optimization runs, and finalize again if necessary.

An assortment cannot be part of an assortment set that has been finalized. In such cases, the rollback menu option is disabled.

When you roll back an assortment to Ready for SO, you cannot export it but you can finalize eligible runs that are associated with the assortment that were not finalized before. In addition, once you have rolled the assortment back to Ready for SO, you can create new runs that are based on planogram sets associated with the assortment, something you cannot do when the assortment is in status of Finalized or Exported.

# **Assortment Analysis**

Assortment Analysis is available for an assortment if one or more of the runs associated with that assortment have been approved. Such runs have a status of Approved or Finalized. CMPO users and SO analysts have permission to conduct this analysis. The SO Super User can access this screen as read-only.

The Assortment Analysis screen can be used to:

- determine how much of a specific assortment has not been optimized
- examine the aggregated results of the approved runs for a specific assortment
- finalize the optimized results
- export the results

To access Assortment Analysis, select an assortment from the Assortment List that has a status of Ready for SO or Finalized. You see the Assortment Analysis screen. This screen consists of three distinct areas.



#### **Assortment Summary**

This section of the Assortment Analysis screen displays a subset of the information contained in the Assortment List. The information describes the assortment you selected.

Figure 1-2 Assortment Summary




#### **Select Runs for Analysis**

This section displays the runs for the assortment you selected. The Available Runs lists all the runs associated with the assortment whose status is Approved or Finalized. Only approved or finalized runs appear here. The Selected Runs lists the runs whose results you are interested in viewing. Overlaps may exist across selected runs. In that case, results from the most recently approved or finalized run take precedence over other runs with the same sku/store combination.

The Selected Runs list is also used to control which runs become finalized. If you select more than a run that covers the same product/location, you will only see results from the run with the most recent results data.

Figure 1-3 Select Runs for Analysis



To move all runs from the Available Runs list to the Selected Runs list, click the double arrow.




To move a select group of runs from the Available Runs list to the Selected Runs list, highlight the run or runs you want in the Available Runs list and click the single arrow.

To moves runs from the Selected Runs list to the Available Runs list, you should reverse this process.

#### **Run Results**

To display the results of a run in the Run Results table, highlight the run, and click the **View Results** button. (Note that some columns are hidden so that the figure fits on the page.)

Figure 1-4 Run Results



By default, the results are displayed for all data. To display the data at different levels of aggregation, use the **Show** drop-down list. You can choose from the following options:

- All data
- Roll up to Assortment Cluster (a single line is displayed for the entire cluster)
- Roll up to Product. Product: Results are displayed at the Assortment Cluster/Product level. You see one line for each product within each cluster.
- Roll up to Planogram Set. Results are displayed at the Assortment Cluster/Product/ Planogram Set level. You see one line for each planogram set that a product belongs to within an assortment cluster.

To clear the display, click the **Clear Selection** button. This clears the results from the results table and moves all of the runs in the Selected Runs list back into the Available Runs list (resets the user selection).

#### **Results Table**

The Results Table displays the following information at the aggregation level you selected. Note that each aggregation level displays only a subset of the information listed in the table.



Table 1-9 Results Table

Column Name	Description	Displayed at Aggregation Level
Assortment Cluster	The name that identifies the cluster.	All, Cluster, Product, Planogram Set
Product Code	The code assigned to the product.	All, Product, Planogram Set
Product Name	The name that identifies the product.	All, Product, Planogram Set
Planogram Set	The name that identifies the planogram set. The name is a concatenation of the subcategory name and the season name.	All, Planogram Set
Store Code	The code assigned to the store.	All
Store Name	The name that identifies the store.	All
Run ID	The ID that identifies the specific run. This is useful for assortments with more than one run.	All
Store Count	Tells the user how many stores the data from that row represents.	Product, Planogram Set
Stores with Facings	The number of stores whose facing count is greater than 0 (see Store Count description).	Product, Planogram Set
Facing Count	The facing count.	All, Cluster, Product, Planogram Set
Sales Units	The number of the standard sales category for a product.	All, Cluster, Product, Planogram Set
Sales Revenue	The amount of revenue for the product.	All, Cluster, Product, Planogram Set
Gross Profit	The difference between sales revenue and cost.	All, Cluster, Product, Planogram Set
Lost Sales Units	The lost sales units.	All, Cluster, Product, Planogram Set
Demand	The demand.	All, Cluster, Product, Planogram Set

#### **Finalizing an Assortment**

Which runs are finalized is based on which runs are used to generate the results data (the set of unique Run IDs in the View Results table). In order to determine the runs used to generate the data, the most current run for each product/store is determined. For example, when you view the results for All, you may see records that have different Run IDs.

The Selection Recommended for Runs should include all runs used to generate the results. A run must be in this list and in the Selected Runs list in order to become finalized when the assortment is finalized.

Once you are satisfied with the results and finalize an assortment, it is available for export to CMPO and Space Planning.

Once an assortment is finalized, the status as displayed in the Assortment List changes to Finalized.


To finalize an assortment, open it in the Assortment Analysis screen, select the runs you want to finalize, and click the **Finalize** button.



#### **Exporting the Run Results**

Once an assortment is finalized, the Export button is enabled and the Finalize button is disabled. Click the **Export** button in order to export the results. Once the assortment is exported, the results of the export are displayed in the Assortment Analysis table, and you can no longer select the runs for analysis. At this point, the Assortment Analysis display consists only of the Summary and the Results. The Select Runs for Analysis section is not displayed.

Figure 1-5 Assortment Analysis After Export



Once an assortment is exported, the status of the run as displayed in the Assortment List changes to Exported. The status is also shown on the Assortment Analysis screen, in the Summary section.

Once the assortment is finalized and exported, it is no longer available in the Select Planogram Set in Execute Space Optimization.

An assortment cannot be part of an assortment set that has been finalized. In such cases, the export button is disabled.

The runs that are finalized may represent a subset of the group of approved runs.

#### **Assortment Analysis Metrics**

The metrics displayed in the Assortment Summary list and in the Run Results list can be different. This can occur when there is more than one run, as the run results roll-up to Space Cluster or Store (optimization location) and the assortment analysis rolls up to Assortment Cluster.

Specifically, the metrics Units, Sales Revenue, Gross Profit and Lost Sales Units obtained from run results are summarized across all optimization location for all stores. These values match the assortment analysis rollup to assortment cluster when that run is the only selected. The metrics Facing and Demand actually match but are presented at different levels within the two screens. The run results bottom panel - included products shows those values as an average per store, while the assortment analysis screen shows those values just as the other metrics: across all the stores within the cluster.

# **Optimization List**

The Optimization List is the dashboard for the ASO runs. In this tab, you can see a list of all existing runs, along with details that describe each run. The list includes runs created by other



users, which you can open in read-only mode. You can create a run, copy a run, open a run, or delete a run.

# Optimization List Interface

The optimization list, shown in Figure 1-6, includes the columns described in Table 1-10.

Figure 1-6 Optimization List




Table 1-10 Optimization List

Field	Description
Run Name	The Run Name is built by concatenating the internal Run ID and the user-provided name.
Created By	The login ID of the user who created the run.
Planogram Set	A description of the POG set. The name is a concatenation of the subcategory name and the season name.
Location Level	The location level selected for optimization (Store or Space Cluster).
Optimized On	The date when the run was optimized.
Status Update	The date when the status was last updated.
Run Status	The current status of the run. Values include Setup in Progress, Submitted, Running, Complete, Data Error, Technical Failure, Approved, and Finalized. See <a href="Table 1-11">Table 1-11</a> for details about each status.
Assortment Count	The number of assortments to which the run applies (this is based on how many assortments include the planogram set that is set for the run)
Description	The user-provided description for the run.



Table 1-11 Run Status Description

Status	Description
Setup in Progress	User is setting up the run, which has not yet been submitted for optimization.
Submitted	The user has submitted the run for optimization.
Running	The run optimization process is currently running.
Complete	The optimization process is complete, and the run results are ready for review.
Data Error	Execution was suspended/aborted due to data errors.
Technical Failure	An unexpected condition (technical) has caused the optimization run to abort execution.
Approved	The run results have been reviewed and approved for assortment analysis.
Finalized	The run results have been included in the assortment finalization and are ready for export to other applications.

#### Create a Run

To create a new run, click the **Create Run** icon. You are taken to the Optimization Setup stage in the Execute Space Optimization tab.

In order to create a run, you must have either Micro-space opt analyst permission or analytical super user permission.

# Copy a Run

To copy an existing run, highlight that run in the displayed list and click the **Copy Run** icon. Alternatively, you can also open the run you want to copy and then choose Save As from Action menu. You are taken to the Optimization Setup stage in the Execute Space Optimization tab. The fields are populated with copies of all inputs and data. Any existing results are not included. The list of runs is updated with a run that has a new ID; all other fields match the existing run. Only the micro space opt analyst and analytical super user can create new runs.

### Open a Run

To edit an existing run, highlight that run in the displayed list and click the run ID. Any user can open a run; however, only users with micro space opt analyst or analytical super user permissions can open a run in edit mode. Edit mode is only allowed for runs that a user created and only when the run does not have a status of Running, Approved, or Exported. All other runs are opened in read-only mode.

#### Delete a Run

Runs can be deleted depending on the status of the run and the permissions a specific user has.

A user with Administrator permissions can delete any run except for one that has a status of Setup in Progress.



Users with micro space opt analyst or analytical super user can delete any runs they have created that do not have a status of Running, Approved, or Exported. They cannot delete runs created by another user.

More than one run can be selected for deletion at the same time.

# **Execute Space Optimization**

The Execute Space Optimization tab provides a series of four stages that you progress through in order to set up, run, and analyze the results of the optimization run:

- Optimization Setup. Used to pick a planogram set, the locations, and the optimization level.
- <u>Fixture and Product Data</u>. Used to view or change fixtures and product merchandise settings.
- Objective and Constraints. Used to view or choose optimizations, objectives, and constraints.
- Results and Analysis. Used to view results and override, approve, or revisit prior steps in order to make changes.

# **Optimization Setup**

The Optimization Setup stage is used to pick a planogram set, the locations, and the optimization level. It is organized into three major sections: the Summary section, the Setup section, and the Review Optimization Locations section.

During this stage, if a planogram does not have detailed shelf information, ASO Cloud Service, using the smart start process, automatically assigns shelves to these partial shelf fixture planograms (PSFP) using configured parameters. These planograms are flagged in the Partial Fixtures column in the Planogram Fixtures tab (see <u>Fixture and Product Data</u>).

This tab is read-only if the run has been submitted to the system, if the user does not have permission to edit runs, or if the user has permission to edit runs but not create runs.

After you have made your selections, you can go to the next stage by clicking the **Next** button, submit the run for optimization, or validate the data. Use the **Action** menu to access Submit and Validate. If you submit the run for optimization at this point, the default rules and settings are used.

# Summary

The Summary section, shown in <u>Figure 1-7</u>, identifies the run you are configuring. This section is populated once you provide the required information in the <u>Setup</u> section. It contains the fields listed in <u>Table 1-12</u>.

Figure 1-7 Summary



The Summary section is displayed at the top of each tab in the Execute Space Optimization stage.



Table 1-12 Summary Section Fields

Field	Description
Description	The name for the run.
Created By	The user ID of the person who has created the run.
Created On	The date when the run was created.
Status	The status of the run. Values include Setup in Progress, Running, Complete, Approved, and Finalized.
Status Update	The date when the status for the run was last updated.
Optimized On	The date when the run was last submitted for optimization.
Planogram Set	The name of the planogram set, which is selected from the Select Planogram Set dialog box. A planogram set name is a concatenation of the subcategory name and the season name.
Assortment Name	A comma-separated list of all assortments associated with the run.

### Setup

The Setup section, shown in <u>Figure 1-8</u>, is used to define and configure the run and provides access to dialog boxes that you use to select the Planogram sets and the optional Template to use for the run. In addition, you identify the Location Level for the run.

Figure 1-8 Setup



Click the **Save** button to save changes to the Name and Description fields. You also use this button to save changes to the planogram set, location level, and template run fields.

Table 1-13 Setup

Field	Description
Name	The name identifying the run. The name must be 80 characters or less and use alphanumeric characters only. It is case sensitive.
Description	A brief description of the run. The value must be 200 characters or less and use alphanumeric characters only.
Planogram Set	The field displays the name of the planogram set you select for the run. The name is a concatenation of the subcategory name and the season name.
	Click the <b>Pencil</b> icon to access the <u>Planogram Set</u> dialog box, from which you make a selection.
Template Run	The field displays the name of the template you optionally select to use when creating a new run. Click the <b>Pencil</b> icon to access the <u>Template Run</u> dialog box, from which you make a selection.



Table 1-13 (Cont.) Setup

Field	Description
Location Level	Choose the <u>Location Level</u> for the run from the drop-down list. Values are Space Cluster and Store.


#### Use Additional POG Attributes

Use this check box to activate or deactivate the use of the POG configuration in the clustering process.

### Planogram Set

The Select Planogram Set dialog box, shown in <u>Figure 1-9</u>, which you access by clicking the **Pencil** icon adjacent to Planogram Set, lists all the planograms that are available to you for the run. You can select only one.

Figure 1-9 Select Planogram Set



Highlight the appropriate row and click **OK**. If you change this selection after either selecting stores or building optimization location tables, then you must re-select the stores and the optimization locations for those stores.



Table 1-14 Select Planogram Set

E:-Id	Providetion
Field	Description
Planogram Set	The display name for the planogram set. The name is a concatenation of the subcategory name and the season name.
Store Count	The number of stores associated with the planogram set.
Planogram Hierarchy Department	The planogram set belongs within a hierarchy that consists of Department, Category, Subcategory, and Season.
Planogram Hierarchy Category	The planogram set belongs within a hierarchy that consists of Department, Category, Subcategory, and Season.
Planogram Hierarchy Subcategory	The planogram set belongs within a hierarchy that consists of Department, Category, Subcategory, and Season.
Planogram Hierarchy Season	The planogram set belongs within a hierarchy that consists of Department, Category, Subcategory, and Season.
Assortment Details Product Category	A comma-separated list of the assortment IDs that the planogram set applies to.
Assortment Details ID	The external ID of the planogram set.
Assortment Details Name	A comma-separated list of the assortment external IDs that the planogram set applies to.

### Template Run

The Select Template Run dialog box, which you access by clicking the **Pencil** icon adjacent to Template Run, lists all the previous runs that are available to you to use as a template in creating a new run. You can select only one. Highlight the appropriate row and click **Save**. The new run you initialized uses values and settings that were used in the template run and apply to the new run. This is optional. You can use the No Template button to clear the template selection.

Table 1-15 Select Template Run

Field	Description
ID	The ID that identifies the run.
Name	The name of the run.
Description	A brief description of the run.
Planogram Set	The planogram set associated with the run.
Created By	The user ID of the person who created the run.
Run Status	The status of the run. Values include Setup in Progress, Running, Complete, Approved, and Finalized.
Status Update	The date when the status for the run was last updated.

#### **Location Level**

The location level identifies the level at which the optimization occurs. You select either Space Cluster or Store from the drop-down list. If you change the value of this field after building the optimization locations, then the optimization locations are re-built using the store you selected and at the new location level.




#### Use Additional POG Attributes

Use this check box to enable space cluster generation based on the product list and POG length (base criteria) plus the additional POG attributes height, depth, and fixture type. If you select this check box and save the changes, the optimization location tables are refreshed based on the new setting.

## **Review Optimization Locations**

The Review Optimization Locations table, shown in <u>Figure 1-10</u>, displays the optimization locations for the optimization.

Figure 1-10 Review Optimization Locations



You can use this table to edit the list of existing locations or add new locations. The locations are listed in a tree structure that shows the hierarchy the optimization locations are part of. If the location level is set to Space Cluster, then the lowest level of the tree is space cluster. If the location level is set to Store, then the lowest level of the tree is store.

**Table 1-16 Review Optimization Locations** 


Field	Description
Location Tree	Displays the node name in the optimization location hierarchy tree. The lowest level is either space cluster or store.
Location Description	A brief description of the optimization location hierarchy node.
Optimization Locations	The number of optimization locations under the optimization location hierarchy node. The lowest level is always a value of 1.
Store Count	The number of stores in the optimization location hierarchy node. If the location level is store, then it will be a value of 1 for the lowest level.
Product Count	The number of products for the optimization location, based on the associated assortment.
Assortment Time Frame	The start date and end date for which the optimization location's associated assortment is valid, across products.
Planogram Fixture Type	A comma-separated list of unique planogram fixture types that exist for the optimization location hierarchy node.
Planogram Length	A comma-separated list of unique planogram lengths that exist for the optimization location hierarchy node.



#### **Choose Stores**

Click the **Choose Stores** button to add locations to the optimization run. The Selected Stores dialog box, shown in <u>Figure 1-11</u>, lists the stores that you have already selected for the optimization locations.

Figure 1-11 Choose Stores



If you have not yet selected any stores, then no stores are listed and the table is blank. This can occur if you have changed the planogram set for the run or in the case of new runs (in which stores have not yet been added).

The Choose Stores dialog box contains the following fields:

Table 1-17 Choose Stores

Field	Description
Store	The identification for the store. It is a concatenation of the store code and the store name.
Parent Cluster	The name of the cluster that the store belongs to.
Product Count	The number of products that the store carries that belong to the assortment associated with the planogram set that you selected.
Assortment Time Frame	The start date and end date during which the assortment associated with the planogram set you selected is valid.
Planogram Fixture Type	A comma-separated list of the unique planogram fixture types available for the associated planogram set's assortment at the store.
Planogram Length	A comma-separated list of the unique planogram lengths available for the associated planogram set's assortment at the store.

You use the Choose Stores dialog box for adding stores and deleting stores. It is enabled once you provide the required information in the Summary section. To add stores, click the **Add** icon in order to access the <u>Adding Stores</u> functionality. To delete stores, highlight one or more



stores from the Choose Stores list and click the **Delete** icon. You can also click the **Add All Stores** button in order to add all the stores for which the planogram set you selected applies.


When you click **OK** in the Choose Stores dialog box, the list of selected stores is saved and the optimization locations are built or re-built. As long as the run is in a state in which the optimization locations can be edited, you can update the list and re-build the optimization locations.

When you click **Cancel** in the Choose Store dialog box, all the changes you have made to the list of selected stores are reverted and no changes are made to the optimization locations.

### Adding Stores

You add stores through the Select Stores dialog box, which you access by clicking the **Add** icon in the Choose Stores dialog box. The Select Stores dialog box, shown in <u>Figure 1-12</u>, displays a list of stores that can be added to the optimization run, based on the run's Planogram Set value.

Figure 1-12 Select Stores



The Select Stores dialog box contains the following fields:

Table 1-18 Select Stores

Field	Description
Location Tree	The name of the location hierarchy node. If it is the lowest level, it is space cluster or store.
Description	A brief description of the location hierarchy node.
Store Count	The number of stores in the optimization location hierarchy node. If the location level is store, then it will be a value of 1 for the lowest level.
Product Count	The number of products in the location, based on the associated assortment.



Table 1-18 (Cont.) Select Stores

Field	Description
Assortment Time Frame	The start date and end date during which the location's associated assortment is valid.
Planogram Fixture Type	A comma-separated list of unique planogram fixture types for the location hierarchy node.
Planogram Length	A comma-separated list of unique planogram lengths for the location hierarchy node.

### **Contextual Information**

The following information is only available when the optimization locations have been defined.

### Store Lookup

You can use Store Lookup, shown in <u>Figure 1-13</u>, to access information about a store. You must provide the store code, either by entering it into the text field provided or by selecting it from the drop-down list. This list is populated based on the optimization location selected for the run.

Figure 1-13 Store Lookup



Once you select the store, you see the following information:

- Store name
- Optimization location (if location level is Space Cluster)
- Parent cluster

### Space Cluster Lookup

You can use the Space Cluster Lookup, shown in <u>Figure 1-14</u>, to see the list of stores associated with a specific space cluster. You must provide the name of the space cluster, either by entering it into the text field provided or be selecting it from the drop-down list. The list is populated based on the optimization location selected for the run.



Figure 1-14 Space Cluster Lookup




Once you select the space cluster, you see a list of the component stores.

## Charts

Two charts are provided in which you can see the variation in store counts by optimization location and product counts by optimization location. The charts are populated with data once the optimization location has been configured. Figure 1-15 provides an example of the store counts chart and Figure 1-16 provides an example of the product counts chart.

Figure 1-15 Store Counts








Figure 1-16 Product Counts

## Fixture and Product Data

The Fixture and Product Data stage is divided into a Summary section, a Planogram Fixtures tab, and a Product Merchandising Data tab. The Summary section identifies the characteristics of the run. The Planogram Fixtures tab is used to review the available planogram lengths for each optimization location and to update the selected configuration for each available length from a set of configurations for each length. The Product Merchandising Data tab is used to assign merchandising options to products. These assignments can vary by product or optimization location.

This tab can only be edited by the user who created the run and only before the run has a status of Running, Approved, or Finalized.

## Summary

The Summary section, shown in Figure 1-7, identifies the run you are configuring.

Table 1-19 Summary Section Fields

Field	Description
Description	The name for the run.
Created By	The user ID of the person who has created the run.
Created On	The date when the run was created.
Status	The status of the run. Values include Setup in Progress, Running, Complete, Approved, and Finalized.



Table 1-19 (Cont.) Summary Section Fields

Field	Description
Status Update	The date when the status for the run was last updated.
Optimized On	The date when the run was last submitted for optimization.
Planogram Set	The name of the planogram set, which is selected from the Select Planogram Set dialog box.
Assortment Name	The name of the assortment associated with the planogram set.


## Planogram Fixtures

The Planogram Fixtures tab contains two sections: the Locations and Planogram Lengths table and the Available Configurations table.

## Locations and Planogram Lengths

This table, shown in Figure 1-17, displays the run's optimization location and provides metrics about the available planogram configurations for each run.

Figure 1-17 Locations and Planogram Lengths



You can create new lengths, which can be either shorter or longer than the current lengths (subject to validation) and refresh the table display.

Table 1-20 Locations and Planogram Lengths

Field	Description
Space Cluster/Store	The name of the space cluster or store.
Parent Cluster	The name of the parent cluster of the optimization location.
Store Count	The number of stores in the optimization location.
Current Length	The length of the configuration that is currently ready for optimization.
Planogram Length Count	The number of unique planogram lengths in the optimization location.
Configuration Count	The number of planogram configurations in the optimization location.
Planogram Fixture Type	A comma-separated list of the unique fixture types present across all configurations that are ready for optimization. This list includes fixture types that have been created by the user.




Table 1-20 (Cont.) Locations and Planogram Lengths

Field	Description
Partial Fixtures	Y indicates that the planogram does not have detailed shelving data and that the fixture configuration has been generated based on configuration parameters.
	N indicates that the planogram has complete shelving data.

**Planogram Setup** 


Figure 1-18 Planogram Setup Button



Select **Planogram Setup** to access the Planogram Setup dialog box. This button in enabled after you select at least one optimization location row from the table. The Planogram Setup dialog box contains the parameters used during the smart setup process to generate the Partial Shelf Fixture Planogram (PSFP). You can edit these parameters and rerun this process using this dialog box. These parameters are described in <u>Table 1-21</u>. Note that the allowable minimum and maximum values permitted in this dialog box are configured in the database.



Figure 1-19 Planogram Setup Dialog Box



**Table 1-21 Planogram Setup Parameters** 

Field	Description
Shelf Placement Using	This drop-down menu as two options, Height Percentile and Absolute Height. The choice you make between these two options determines the types of values (percentage or numeric) used by some of the parameters and which parameters are displayed.
Max Gap Between Shelves	When using Height Percentile: Select the Nth percentile from the distribution of product heights in the assortment as the maximum gap between two shelves. When using Absolute Height: Use the provided value as the maximum gap between two shelves
Min Gap Between Shelves	When using Height Percentile: Select the Nth percentile from the distribution of product heights in the assortment as the minimum gap between two shelves. When using Absolute Height: Use the provided value as the minimum gap between two shelves
Interior Step Size	When using Height Percentile: Reduce the height percentile to use for each subsequent shelf placement (e.g., with a max of 100% and step of 20%, the next shelf placement will use the 80th percentile of product heights to determine the gap) When using Absolute Height: Determine the gap between interior shelves using the step size
Absolute Min Gap	The absolute minimum gap between two shelves, regardless of product height percentiles.
Slot Spacing	Distance between slots in the bay. Final shelf placement will round to the nearest slot position.



Table 1-21 (Cont.) Planogram Setup Parameters

Field	Description
Shelf Thickness	The thickness of all shelves placed using the Smart Start Process. Shelf thickness is considered when calculating the gaps between shelving.

The following buttons are available in this dialog box:

- **Reset** Use this button to update the values for all the parameters to the configured default values. You must then click **Submit** to rerun the smart setup process.
- **Submit** Use this button to rerun the smart start process for the optimization locations you selected, based on the parameter values you entered here. When you click this button, the dialog box closes and the available configurations table is refreshed with the new configurations generated by the smart setup process. The new values that you provided for the parameters are saved at the optimization location level.
- Cancel Use this button to close the dialog box without making any changes.

If some of the locations you select do not have partial fixtures, they are not processed by the smart setup process. You will see a message if this occurs.

If some of the locations you select also have overrides that apply, these overrides are also applied. You will see a warning message if this is the case.

#### **Planogram Setup Shelf Placement**

When planogram setup parameters are submitted, the system calculates shelf positions using the selected process (percentile or absolute). The shelf placement rules for each process are summarized in Table 1-22 and Table 1-23 in the order in which they are applied.

Table 1-22 Height Percentile Shelf Placement Rules

<b>Shelf Position</b>	Rule Description
Top Shelf	Place the shelf at (fixture height - (top shelf stacking limit + shelf thickness)), rounded down to the nearest slot position.
Bottom Shelf	The bottom shelf goes in position 0.
Interior Shelves	Starting from the bottom, calculate the gap to the next shelf using product height percentiles. The first interior shelf is placed using the product height at the Max Gap percentile, and each subsequent gap is decreased based on the step size percentile, rounded up to the nearest slot.

Table 1-23 Absolute Height Shelf Placement Rules

Shelf Position	Rule Description
Top Shelf	Place the shelf at (fixture height - (top shelf stacking limit + shelf thickness)), rounded down to the nearest slot position.
Bottom Shelf	The bottom shelf goes in position 0.
Interior Shelves	Starting from the bottom, calculate the gap to the next shelf using the max gap values and step size. The first interior shelf is placed using the max gap size, and each subsequent gap is determined by the step size, rounded up to the nearest slot.




The same process is applied to all empty bays in the planogram, such that multiple bays of the same height have identical shelving. Other fixture types (such as pegboards) are not considered during this process, and bays that already have fixtures are not modified. After the process has been run, the user can override the results by editing the planogram directly. See Fixture Overrides for details.

#### **Create Lengths**

Select **Create** from the Actions menu to access the Create Lengths dialog box, shown in Figure 1-20. You use this to create new planogram configurations for the optimization locations you select. This involves stretching or shrinking a configuration that is marked for optimization. In addition, you can add new bays to the right. If you want to create new lengths for a configuration that has not been marked for optimization, you must mark that configuration for optimization. but it must be a loaded configuration, which can be identified by the fact that the Parent Planogram field is empty or null.

Figure 1-20 Create Lengths



#### Stretch

To stretch the length, select the **Stretch** radio button. Stretching changes the planogram by adding length to the last bay (including internal objects). It adds as much length as defined within the Increase By field up to the maximum length.

A new configuration is created that is a copy of the base configuration. The planogram is shrunk by removing the bays from right to left. The length, in generic measurement length units, is adjusted based on the bays that are removed. That copy is then modified based on the values you enter in the following two fields:



Table 1-24 Create Lengths: Stretch

E: Ald	Paradiation .
Field	Description
Increase By	Use to specify how much to stretch the base configuration in order to create the new configuration. The value must be less than or equal to the value you enter in the Maximum Length field. The unit of measurement is agnostic.
Maximum Length	Use to specify the maximum length possible for the new configuration. The default value that is displayed is configurable during implementation. You can change the default value, but the new value must be less than or equal to the default.

### **Add Bays**

To add bays, select the **Add Bays** radio button. The add bay process creates a copy of the right-most bay, including the fixtures, shelves, pegs, and freezers. The copy is added after the last existing bay on the right. You determine the number of copies added by entering the appropriate value into the dialog box, as described in <u>Table 1-25</u>.

Table 1-25 Create Lengths: Add Bays

Field	Description
Number of Bays to Increase	Indicates the number of bays to add. Must be an integer value.
Maximum Number of Bays	Indicates the maximum number of bays the new POG is permitted to have. This adds as many bays as indicated in the Number of Bays parameter, as long as the overall bay count for the POG does not exceed the maximum value provided for this parameter. Must be an integer value.

Note that adding bays has the effect of increasing the number of shelves, which in turn changes the count of shelves displayed in the UI. Other metrics may also change.

#### **Shrink**

To shrink the length, select the **Shrink** radio button. Shrinking changes length (decrease) by eliminating starting from the last bay as many bays as defined by the Decrease Number of Bays, making sure that at least the minimum number of bays remain.

A new configuration is created that is a copy of the base configuration. The changes are made to the bays (not to the length). The copy is modified based on the values you enter in the following two fields:

Table 1-26 Create Lengths: Shrink

Field	Description
Decrease Number of Bays By	Use to specify, in terms of the number of bays, how much to shrink the base configuration in order to create the new configuration.
Minimum Number of Bays	Use to specify the minimum number of bays for the new configuration. The default value that is displayed is configurable during implementation. You can change the default value, but the new value must be less than or equal to the default.





If the values you specify are the same as those for a configuration (same parent planogram and same length), no new configuration is created. If the values you specify do not fall within the defined minimum and maximum values for shrinking or stretching, the new configuration will be defined by the minimum or maximum value instead.

The new configuration is marked for optimization automatically by the system. Other configurations with the same length are un-marked. If the new configuration is actually the same as the existing one, the existing configuration is marked for configuration.

### **Fixture Overrides**

You can make certain modifications to the run-specific POG data that is used in optimization. These modifications include adding, deleting, editing, and moving shelves associated with shelf fixtures as well as restoring prior settings.





Fixture overrides exist at the optimization level. This means that store-level optimization requires store-by-store fixture overrides and cluster level optimization requires cluster-by-cluster fixture overrides.

To make these modifications, highlight the space cluster of interest and click the **Goggle** icon. An empty planogram is displayed. Right-click on a shelf to access the Edit dialog box.



Empty Planogram 75 for SC\_00001 with Length 144

Figure 1-22 Edit Dialog Box for Fixture Overrides

#### Add

You can add a new shelf to an existing fixture. To do this, select the fixture and then use the right-click menu to access the Add functionality. You see a dialog box the shows defaults. You can change the depth, thickness, and elevation of the new shelf. Note that the new shelf must fit within the existing fixture and it cannot overlap with other shelves.

#### **Delete**

You can delete a shelf from an existing fixture. To do this, select the shelf you want to delete and then use the right-click menu to access the Delete functionality. You will be asked to confirm the deletion.

After you delete the shelf, the space where the shelf existed will no longer show a shelf. If a bottom shelf was deleted, then the shelf and the space up to the next shelf (or top of fixture if no shelves) will be replaced by a grey background.

#### Edit

You can edit an existing shelf. To do this, click on a shelf and use the right-click menu to access the Edit functionality. You see a dialog box where you can change the depth and the thickness of the shelf.

#### Move

You can move an existing shelf to a new location. To do this, select the shelf you want to move and use the right-click menu to access the Move functionality. You see a dialog box that you can use to enter a new value for elevation.

#### Restore

You can restore a POG to the most recently loaded or updated version of that historical POG, based on the most current data feed updates made to the historical POG configuration. You




cannot restore POGs that were created per macro changes. In such cases, you can delete the run and start over with the most recently loaded or updated version of that historical POG.

## **Available Configurations**

This table, shown in <u>Figure 1-23</u>, displays details about the configuration available for the row you select in the <u>Locations and Planogram Lengths</u> table. If you select more than one row, you will see the message "No Data to Display."

Figure 1-23 Available Configurations



The Available Configurations table contains the fields listed in <a href="Table 1-27">Table 1-27</a>.

Table 1-27 Available Configurations

Field	Description
Optimize	Indicates that the configuration is marked for optimization.
Planogram ID	The ID that identifies the configuration (planogram).
Parent Planogram	The base planogram configuration used to create the new configuration. It is always a loaded configuration. The value is Null for an externally loaded configuration.
Planogram Fixture Type	A comma-separated list of the unique fixture types in the configuration.
Planogram Length	The length of the planogram.
Store Count	The number of stores that use the configuration for this run's assortment.
Planogram Length/Height/ Depth	The dimensions of the configuration.
Count of Shelves/Pegboards/ Freezer Chests	Count for the number of each type of fixture that exists in the configuration.

You can perform the following actions with respect to the Available Configurations table. You can initiate each action from the Actions menu or in some cases by clicking the appropriate icon.

### **Mark for Optimization**

You must mark a configuration to make it available for optimization. Only marked configurations are displayed in the Results and Analysis tab. Note that only one configuration for a given length can be marked for optimization. If one configuration for a given length is currently marked for optimization, and you select another configuration of the same length, the first configuration is un-marked.



#### **Delete**

You can delete any user-created lengths (identified by non-null values in the parent Planogram column) in the table. If you delete a configuration that is marked for optimization, all configuration of that configuration's length will be deleted.

#### **View Configuration**

You can view a diagram of the selected configuration by clicking the **View Configuration** icon.

#### **Compare to History**

Click the **Compare to History** icon to see a diagram of the historical planogram used for the selected configuration.

### Contextual Information

A chart is provided that displays summary data for the planogram lengths that are being used for the optimization. This information can help you understand what the current macro space allocation is and what has been added.

Three series for this chart are available. One series shows the count of current lengths and a second series shows the count of added lengths for a given planogram length. If there are no added lengths, then the chart should only show the current lengths. The count is across all optimization locations. The total count of all current lengths should be the number of optimization locations. You can also see product heights, charted by percentage or numeric values, and representing the entire run.

## **Product Merchandise Data**


The Product Merchandise Data tab contains two main sections: The Select Products table and the Merchandising Options table. This stage addresses how products are placed on fixtures.

### Select Product

This table, shown in Figure 1-24, lists all available products. Each product is identified by the details of its hierarchy (level 1-3, department, class, and sub-class), as well as product name and product code.




Figure 1-24 Select Product



## **Merchandising Options**

This table, shown in <u>Figure 1-25</u>, displays the merchandising options for all optimization locations for the product you select in <u>Select Product Table</u>. A merchandising option is the combination of fixture type, display style, main orientation, and capping orientation.

Figure 1-25 Merchandising Options



<u>Table 1-28</u> lists the fields for Merchandising Options.

**Table 1-28 Merchandising Options** 

Field	Description
Space Cluster/Store	Indicates the location level for the product.
Parent Cluster	The name of the parent cluster.
Planogram Fixture Type	A comma-separated list of the unique fixture types in the configuration.
Product Fixture Assignment	The type of fixture.
Display Style	The type of display unit.
Main Orientation	How the product faces the front of the fixture.



Table 1-28 (Cont.) Merchandising Options

Field	Description
Nesting Flag	Indicates that the product will be nested.
Stack and Cap Style	Indicates the stacking and capping style to be used for the product.
Capping Orientation	The orientation for products that are stacked.
Max Units High	Sets the limit for the number of the product unit's vertical height.

You can edit the merchandising options if you have the appropriate permissions.

- Select a product from the Select Product table.
- 2. Select one or more optimization locations from the Merchandising Options table.
- 3. Click the **Edit** icon to access the Edit Merchandising dialog box.
- 4. You see the possible options for each of the Merchandising Options that are available for the product you selected. For each option you select the **Select** check box in order to edit that option. The columns you can edit correspond to the columns that are displayed in the table.

### Contextual Information

The following three sections providing additional information about product merchandising. The contextual information area is located on the right side of the UI. Normally, this area is hidden to provide more room for the main frames, so you must click the small arrow in the middle of the margin to expand the section. Once the section is expanded, you will see the data elements mentioned in the contextual panel.

### Product Size Data

This table, shown in Figure 1-26, displays the sizes of the products for each of the display styles as well as the related spacing data. The data that is displayed depends on the product you select from the Select Product table. The data includes length, height, depth, finger space beside, finger space above, finger space behind, inter-product gap, and units per display style.

Finger space beside refers to the space that is needed by a specific product on the left and right side of each unit.

Finger space above refers to the space that is needed by a specific product between the top of a unit and the bottom of the shelve above it.

Finger space behind refers to the space that is needed by a specific product to the front and to the back of a unit.



Figure 1-26 Product Size Data

Product Size Data	
Product Code - 1234747  Display Style   Single or	100
Metric	Value
Length	4.13
Height	12.00
Depth	4.13
Finger Space beside	0.25
Finger space above	0.25
Finger space behind	0.00
Interproduct Gap	0.50
Units per display style	0.00

### **Product Details**

This table, shown in Figure 1-27, describes the overall demand and replenishment data for the selected product. The data displayed is static and is based on the product you select from the Select Product table.

- Average Demand Data. The size of the histogram bar represents the number of optimization locations.
- Price. The size of the histogram bar represents the number of optimization locations.
- Casepack Size. The size of the histogram bar represents the number of optimization locations.
- Replenishment Frequency. The size of the histogram bar represents the number of optimization locations.



Product Code - 1234747

Chart Avg. Demand Data

38.5-46.

10 🛊 🚱

55.4-63. 46.9-55.

APS Demand per Week

63.8-72.

Figure 1-27 Product Details

### **Location Statistics**

1

**Bin Count** 

This table, shown in Figure 1-28, describes the user demand and replenishment data for the selected product and optimization location. You can use this information to help in making decisions at the lowest level. The data includes store count, APS demand, price, case pack size, replenishment frequency, Item Performance Index (IPI) score, and priority. The data displayed is based on the product you select from the Select Product table and the location you select from the Merchandising Options table.

80.6-89.0

72.2-80.6

89.0-97.4



Figure 1-28 Location Statistics

<ul> <li>Location Statistics</li> </ul>	
1234753 / SC_00001	
Metric	Value
Store Count	3
APS Demand	35.247
Price	6.8704
Casepack size	6
Replenishment frequency	2
IPI score	1.1774
Priority	Optional

## Demand and Replenishment Data


The Demand and Replenishment Data tab lets you refresh the demand and replenishment parameters, make overrides to selected parameters, and understand the replenishment settings and their effects on results. This tab provides a Select Product table that displays all available products and a Demand and Replenishment Options table that displays the replenishment details for the product you select in the list of available products.

### Select Product Table

The Select Product table lists the available products and includes the following information about each product: Department, Class, Subclass, Product Name, and Product Code. When you select a specific product from this table, the Demand and Replenishment Options table is populated with the replenishment details for the product you select.



Figure 1-29 Select Product Table



#### **Action Menu**

The Action menu provides access to two functions: Demand and Replenishment.

Click **Demand** to refresh all the underlying demand data for all the products in the current run. You see updated data derived from data feeds that occurred after the most recent run was created.

Click **Replenishment** to refresh all the underlying replenishment data for all the products in the current run. This action overrides any changes you have made to replenishment data.

#### **Refresh Button**

The **Refresh** button provides the same functionality as the Action menu.

Click **Demand** to refresh all the underlying demand data for all the products in the current run. You see updated data derived from data feeds that occurred after the most recent run was created.

Click **Replenishment** to refresh all the underlying replenishment data for all the products in the current run. This action overrides any changes you have made to replenishment data.

## Demand and Replenishment Options Table

The Demand and Replenishment Options table displays one row for each location that carries the product you select in the Select Product table. Each row contains the aggregated data for all the stores in that optimization location.



Figure 1-30 Demand and Replenishment Options

Demand and Replenishment Options for 1234582 - Folgers Breakfast Roast Non-Flavored De-Caffeinated 12 oz Can Freeze Detach Actions - View - Format -**₩rap Facings** Days Avg. Avg. Standard **Parent** Reple Standard Store Store Deviation Lift of Casepack Frequ Cluster Demand Deviation Booster Parameter Sales 72 - 1039 Ev... 11.611 0 Premium - Sm... 3.408 0 73 - 1040 Su... Premium - Sm... 11.611 0 0 7 6 3.408 1 74 - 1041 Reno Premium - Sm... 11.611 3.408 0 6 1

The following information is displayed:

Table 1-29 Demand and Replenishment Options Table


Column Name	Description
Space Cluster	Optimizations are run at the store level or the space cluster level. A space cluster is an ad hoc group of stores with the same assortment cluster, product list, and current planogram length.
Parent Cluster	The name of the cluster that the store belongs to.
Average Store Demand	This is a weekly average.
Average Standard Deviation	A higher value indicates the need for higher safety stock to meet service levels.
Standard Deviation Booster	This is calculated across all stores in the optimization location.
Facings Lift Parameter	The impact of facings on demand.
Days of Sales	The number of days in a week that are available for store sales.
Casepack	This is calculated as a weighted average of store casepacks. It is weighed by total adjusted store demand within an optimization location. The number of units in a case.
Replenishment Frequency	The number of replenishments per shelf per week.
Replenishment Type	DC/Vendor or Backroom.
Transit Time	The number of days an order takes to go from the source location to the shelf.
Replenishment Trigger	Demand-based, target capacity-based, or case pack-based.
Trigger Parameter	Trigger value for replenishment trigger.

## **Editing the Demand and Replenishment Options Table**

To edit the demand and replenishment data in the table, select the row or rows containing the data you want to edit and then click **Edit**. You see the following dialog box.



Figure 1-31 Edit Replenishment Data



You can edit the following fields. If you leave a field blank, then no changes will be made to that value.

Table 1-30 Edit Demand and Replenishment Data

Field Name	Description
Casepack	Value must be greater than zero.
Replenishment Frequency	Value must be greater than zero.
Transit Time	Value must be greater than zero.
Replenishment Trigger	Choose from the following: Do Not Change, Cover Demand, Percent Capacity, Casepack Fit.
Trigger Parameter	Value must be a percentage greater than zero and less than or equal to 100.

Click **Save** when you are finished editing the replenishment data. The data displayed in the Demand and Replenishment Options table is updated. The contextual information is also updated.

### Contextual Information

The Product Detail chart illustrates the overall demand and replenishment for the selected product. You can select the type of data to display from the drop-down menu: Average Demand Data, Standard Deviation Booster, Facings Lift Parameter, Days of Sales, Casepack Size, Replenishment Frequency, Replenishment Type, Transit Time, Replenishment Trigger, and Trigger Parameter.



# Objective and Constraints

The Objectives and Constraints stage is used to modify or set the constraints (business rules) for an optimization run and to display the settings associated with the run. You specify three types of optimization constraints, product level constraints, product group constraints, and planogram constraints. Even though all constraints are ultimately applied at the optimization location level, you generally set or review the data at higher location levels.

In addition, you also pick an objective for the optimization. The objective defines what metric is used as the goal of the optimization.

Once you are satisfied with all the settings in this stage, you can validate a run or submit the run for optimization. The run closes and the optimization list is displayed. When the status for the run is Complete, you can view the results.

## Summary

The Summary view, shown in <u>Figure 1-7</u>, provides identifying information for the optimization run.

Table 1-31 Summary Section Fields

Field	Description
Description	The name for the run.
Created By	The user ID of the person who has created the run.
Created On	The date when the run was created.
Status	The status of the run. Values include Setup in Progress, Running, Complete, Approved, and Finalized.
Status Update	The date when the status for the run was last updated.
Optimized On	The date when the run was last submitted for optimization.
Planogram Set	The name of the planogram set, which is selected from the Select Planogram Set dialog box.
Assortment Name	The name of the assortment associated with the planogram set.

## Objectives and Constraints Summary

When you select the **Summary** radio button, you see the following information displayed.

## Settings Across All Locations and Products


This section contains four panels that display a summary of the settings.

## **Product Constraints**

This table, shown in <u>Figure 1-32</u>, lists each product constraint, along with values for the most common value, the percentage with the most common value, and the percentage of optimization locations that have the most common value. The product constraints include Inclusion, Facing Range, Capacity Range, and Elevation Range.




Figure 1-32 Product Constraints



## Planogram Constraints

This table, shown in <u>Figure 1-33</u>, lists each planogram constraint, along with values for the most common value and the percentage of optimization locations that have the most common value. The planogram constraints include Use Visual Guidelines, Use Product Spacing, Merge Adjacent Bays, and Set Usable Space.

Figure 1-33 Planogram Constraints




### **Product Groups**

This table, shown in Figure 1-34, lists each type of group that is used, along with values for the total number of product group/optimization location combinations for each group and the number and percentage of optimization location that have a group of that type. The product groups include All or Nothing, Match Facings, Same Shelf, and Choose From. This table does not list product groups created at levels above the optimization location, even though those product groups may be inherited by the optimization locations.




Figure 1-34 Product Groups



## Optimization Objectives

This table, shown in Figure 1-35, lists the objective functions that are being used, along with the number and percentage of optimization locations that use each objective function. The objective functions include Maximize Sales Units, Maximize Sales Values, Maximize Margin Value, Maximize Total Sales/On Hand Value, Maximize Sales Units (Weighted), Maximize Sales Value (Weighted), Maximize Margin Value (Weighted), and Maximize Total Sales Value/On Hand Value (Weighted).

Figure 1-35 Optimization Objectives



## Select Locations and Products

When you select the **Details** radio button, this section displays. It consists of two tables: Select Locations and Select Products, shown in <u>Figure 1-36</u> and <u>Figure 1-37</u>. You must select a row from the location tree and a product row in order to display details about your selections in Objectives and Constraints details section.

The Locations table has three levels. When the first level is selected, the product constraints details across all optimization locations are displayed in the Product Constraints table. When



the second level is selected, only the product constraints details for the second level location are displayed. When any optimization location is selected, only the product constraint details for the selected optimization location are displayed. In the same way, the product constrains in the Products table are displayed. Product constraint details are fetched after both the location and the product levels are select, location first and product second.

Figure 1-36 Select Locations





Figure 1-37 Select Products



## **Objectives and Constraints Details**


This section is used to specify optimization constraints that define the business rules that determine acceptable virtual planograms. It has five tabs; each tab displays detailed information that you can modify if you created the run.

### **Product Constraints**

The Product Constraints tab is shown in <u>Figure 1-38</u>. It includes Custom Attributes, which allow the user to select up to three attributes associated with the selected category of products. Select the attributes from the drop-down menus and click **Show Attributes** to add the attributes to the Product Constraints table.



Figure 1-38 Product Constraints



For each product, it defines the current product constraints, as listed in <a href="Table 1-32">Table 1-32</a>.


**Table 1-32 Product Constraints** 

Column	Description
Department	Merchandise/product hierarchy node.
Class	Merchandise/product hierarchy node.
Subclass	Merchandise/product hierarchy node.
Product Name	Product identification.
Product Code	External product code.
Store or Space Cluster Count	Number of stores/space clusters that carry the product.
Inclusion	Supported inclusion values: Must keep (product must not be dropped), Can keep (product can be dropped), and Do not include (product must not be included).
Capacity Range	Type, minimum, and maximum value for capacity range.
Facing Range	Minimum and maximum value for facing range.
Elevation Range	Minimum and maximum value for elevation range.

Click the **Edit Constraints** button to access the Edit Product Constraints dialog box, shown in Figure 1-39. After selecting one or more rows, you can edit the constraints if you created the run and if the run has not been submitted.



Figure 1-39 Edit Product Constraints




Use the drop-down lists, which contain the valid options for each constraint, to change the settings for any constraints, as appropriate. After you complete your edits, select **Save** from the Action menu. The system validates the changes you make and adjusts other settings as necessary. If you enter minimum and maximum values that are inconsistent, you will see an error message and must make changes before you can successfully save your edits.

## **Product Groups**

The Product Groups tab, shown in <u>Figure 1-40</u>, is used to define parent groups, which, when defined at a location node above the optimization location, can be inherited by the optimization locations that are the children of the parent location node.

Figure 1-40 Product Groups



You can add, edit, or delete product groups as well as add products to and delete products from product groups. Inherited groups can also be added or deleted.




**Table 1-33 Product Groups** 

Column	Description
ID	Unique numerical identification for product group.
Name	Name of product group.
Location	Store or space cluster for product group.
Constraint Type	Values are: All or Nothing, Match Facings, Same Shelf, and Choose From.
Constraint Criteria	If Type is Choose From, values are: At Least, At Most, and Exactly.
Constraint Value	If Type is Choose From, then a numerical value is required here.
Inherited Location Count	If the product group belong to either a Level 1 or Level 2 optimization location, the product group can be copied to or referenced by Level 3 optimization locations. This column shows the count of such optimization locations.
Product Count	The number of products in the product group.
Parent Group	If this product group is created by copying or referencing an existing product group of a higher level (1 or 2) then this column shows the ID of parent product group.
Errors	Number of errors for product group.
Warnings	Number of warnings for product group.

#### **Selected Products**

Use this section, shown in  $\underline{\text{Figure 1-41}}$  to add or remove products from a selected product group.


Figure 1-41 Selected Products



You can see and use the product attributes by accessing the Custom Attributes dialog box shown in <u>Figure 1-42</u> when you are creating product groups. When you make a selection, the Product Groups table is populated.




Figure 1-42 Custom Attributes



#### **Inherited Locations**

Use this section, shown in Figure 1-43, to add or remove inherited locations.

Figure 1-43 Inherited Locations



### Visual Guidelines

Visual Guidelines provide product attribute-based vertical and horizontal blocking for placing products on a shelf fixture planogram. You are allowed up to four levels for the blocking criteria. The visual guidelines can be created at the top level (All Locations) for each fixture type; the optimization locations inherit this. In addition, you can edit or modify the optimization location level visual guideline; if you do this, the link to the parent is broken. Each optimization location can have only one visual guideline for a fixture type. You can add, delete, and edit the visual guidelines.

Blocking is defined as horizontal or vertical. Vertical is the default. You can specify primary and secondary blocking criteria. The secondary blocking is optional. If the primary blocking is vertical then the secondary blocking is horizontal; if the primary blocking is horizontal then the secondary blocking is vertical. Horizontal blocking supports pegboards.

Primary and secondary blocking can have up to two attributes each. Each attribute for a specific blocking strategy is defined in the same way, horizontal or vertical. A sequence number is assigned to each attribute value for each blocking level. The sequence numbers



determine the order of the blocks. In ascending order, the blocks are positioned from top to bottom (horizontal) and left to right (vertical). When two are blocks are assigned the same sequence number, the blocks are combined (merged).

#### Example 1:

Primary blocking: Vertical blocking by brand.

Merge blocks: Brand A, Brand B, and Brand C

Additional primary blocking: Vertical blocking by type.

Secondary blocking: Horizontal blocking by size for all vertical blocks.

### Example 2:

Primary blocking: Horizontal blocking by size.


Additional primary blocking: Horizontal blocking by flavor.

Secondary blocking: Vertical blocking by brand for all vertical blocks.

#### **Visual Guidelines Table**

The Visual Guidelines table provides information about each visual guidelines row.

Figure 1-44 Visual Guidelines



The columns for this table are described in Table 1-34.

Table 1-34 Visual Guidelines

Column	Description
Space Cluster/Store	The name of the optimization location.
Parent Cluster	The name of the parent cluster for the optimization location.



Table 1-34 (Cont.) Visual Guidelines

Column	Description
Description	The name of the visual guideline.
Primary Blocking Strategy	Vertical or horizontal.
Primary Attribute	The product attribute used.
Primary Blocks	The first block used for the configuration
Inherited Location Count	The number of space clusters or stores that inherit the parent visual guidelines.
Parent VG Cluster	The ID of the parent visual guideline cluster.

The Primary Block Details table provides additional information.

Table 1-35 Primary Block Details

Column	Description
Shared Configuration	Indicate whether or not two attributes share the same configuration.
Primary Attribute Value	Primary attribute.
Block Sequence	Defines the block and the sequence for that block.
Merge Sequence	Blocks with the same merge value are combined.
Product Count	The number of products in the block.
Sales Units	The average sales units for products in the block.
Sales Revenue	The average sales revenue for products in the block.
Additional Primary Attribute	Additional primary attribute.
Secondary Attribute	Secondary attribute.
Additional Secondary Attribute	Additional secondary attribute.

### **Adding Visual Guidelines**

You can add visual guidelines through the Add Visual Guidelines dialog box. You access this by selecting the **Detail** radio button and clicking the **Add** icon.






Figure 1-45 Add Visual Guidelines

To add visual guidelines, complete the following steps:

- 1. Enter the description of the visual guideline in the Description text box.
- Select the primary blocking strategy, horizontal or vertical, from the Primary Blocking Strategy drop-down list.
- 3. Select the attribute to use for blocking from the Attribute drop-down list. This populates the table with the attribute values. At this point, the values for all sequences are assigned a default value of 1.
- 4. Define the attribute sequence number for each attribute by selecting a value from the drop-down list in the Block Sequence column. This defines the block and the sequence for the block. To define merged blocks, assign the same value to each attribute to be merged.
- 5. Optionally, define the merge sequence value by selecting a value from the drop-down list in the Merge Sequence column. This functionality is only enabled if you have assigned the same sequence number to two of the primary blocks.
- Choose locations from Selected Locations.
- 7. Optionally, prior to saving the primary blocking, you can specify the advanced blocking. To do this, select the attribute value in the table and click the Pencil icon. You see the Advanced Blocking dialog box.






Figure 1-46 Primary Block Configuration

After the primary blocking strategy and attribute are defined, the primary block can be configured. When primary blocking is vertical, then horizontal blocking is specified for each primary block. When primary blocking is horizontal, then vertical blocking is specified for each primary block.

8. When two attributes have the same sequence number, they share the same configuration. If you change one of the attribute's block sequence numbers to an unassigned number, it still maintains that configuration. If you change the attribute's block sequence number to an assigned number, then it takes the new configuration of the block it joins.

The Use Same Advanced Blocking across all Primary Blocks check box functions in different ways, depending on the following:

- When the primary blocking strategy is vertical, the check box is enabled. Check this
  box if you want all of the primary blocks to share the same secondary and additional
  blocking. If you do not check this box, then each primary block is configured
  separately.
- When the primary blocking strategy is horizontal, the check box is disabled. When two
  or more attributes share the same sequence number, all the products that have these
  attributes are combined.
- 9. To configure Additional Primary Blocking, select the attribute from the drop-down list. The table populates with the attribute values. All sequence numbers default to a value of 1. If you select None for the attribute, then blocking at this level is disabled.
- 10. Define the attribute sequence for each attribute value by selecting the sequence number from the drop-down list in Block Sequence. If you assign the same sequence number to more than one attribute, then all the products with these attributes are combined.
- 11. To configure Secondary Blocking, select the attribute from the drop-down list. The table populates with the attribute values. All sequence numbers default to a value of 1. If you select None for the attribute, then blocking at this level is disabled.
- 12. Define the attribute sequence for each attribute value by selecting the sequence number from the drop-down list in Block Sequence. If you assign the same sequence number to more than one attribute, then all the products with these attributes are combined.
- 13. You can only configure Additional Secondary Attributes if you have configured Secondary Blocking. To configure Additional Secondary Attributes, select the attribute from the drop-



- down list. The table populates with the attribute values. All sequence numbers default to a value of 1. If you select None for the attribute, then blocking at this level is disabled.
- 14. Define the attribute sequence for each attribute value by selecting the sequence number from the drop-down list in Block Sequence. If you assign the same sequence number to more than one attribute, then all the products with these attributes are combined.
- 15. Click **OK**. The Add Visual Guidelines table is updated with the selected attributes.
- 16. Click Save to save the configuration. This overwrites any existing visual guidelines configuration for the selected location.
- 17. You can use Visual Guidelines to specify visual guidelines at higher location levels and have space clusters or stores inherit the visual guidelines. For this, you must select a node higher than lowest level in the Locations tab at the top. To specify which space clusters will inherit this visual guideline, select the appropriate space clusters while adding or editing the visual guidelines.

Consider the example shown in Figure 1-47. Two visual guidelines are created at two higher-level nodes: All Locations and AHBaarnII. During the process of adding or editing the visual guidelines, the user has selected different space clusters to inherit this higher-level rule. For example, space clusters SC\_00002 and SC\_00003 inherit the VG created at All Locations (primary attribute = Coffee Tea-Classification), and SC\_00001 inherits the All Locations visual guidelines (primary attribute = Coffee Tea-Flavor).





Figure 1-47 Visual Guidelines Example

### **Editing Visual Guidelines**

You can modify the characteristics of a visual guideline through the Edit Visual Guidelines dialog box. Select a row to indicate which guideline you want to edit and click the **Pencil** icon. You see the Edit Visual Guidelines dialog box.



Figure 1-48 Edit Visual Guidelines




You can modify any values except the Primary Blocking Strategy and the Primary Attributes following same approach you use to create those values. Once you have completed making changes, click **Save** to save your changes and update the Visual Guidelines table. You can click the **Cancel** button to cancel the edits.

## Adding Family Group and Sorting

The Family Groups & Sorting tab, shown in Figure 1-49, is used to define parent product family groups and sort order. These can, when defined at a location node above the optimization location, be inherited by the optimization locations that are the children of the parent location node. In addition, you can define product family group and sort order at the planogram level or at any block level. The hierarchy for how rules are applied to optimization is: All Blocks, Primary (Additional Primary), and Secondary (Additional Secondary). The lower level product family group and sort order are given priority compared to a product family group (PFG) and sort order specified at a higher-level. For example, a user defines one PFG & Sort Order at the all blocks level (or planogram-level) and another at a specific Primary Block level. Then, except for the primary block and its children that were specified as a separate PFG & Sort Order, all other primary blocks (and children) will receive the planogram-level specification. In other words, you can manage the product family group and sort order by exception: Apply the global PFG and Sort order except for this one specific primary block and its children.



Figure 1-49 Family Groups and Sorting



## Manage Family Groups & Sorting Panel

You can add, edit, or delete family groups and sort order as well as specify which space clusters will inherit the product family group and sort order. This panel displays all the family groups defined, and at what location level, for which fixture type and at what block level. It also shows whether the family group and sorting defined at a particular block level is valid or not (for example, the underlying block was deleted for some reason after family group and sorting is defined).

Table 1-36 Family Group and Sort Order

Column	Description
Product Family Group and Sorting ID	Unique numerical identification for product family group and sort order.
Name	Name of product family group and sort order.
Location	Store or space cluster for product family group and sort order.
Fixture Type	Fixture type can be shelf, pegboard or freezer chest.
Inherited Location Count	If the product family group and sort order belongs to either a Level 1 or Level 2 optimization location, the product family group and sort order can be copied to or referenced by Level 3 optimization locations. This column shows the count of such optimization locations.
Parent Group	If this product family group and sort order is created by copying or referencing an existing product family group and sort order of a higher level (1 or 2), then this column displays the ID of the parent product family group and sort order.
Primary Attribute Value	If the family group and sort order is defined for a primary block, then this will be the list of all attribute values (comma separated).
Additional Primary Attribute Value	If the family group and sort order is defined for an additional primary block, then this will be the list of all attribute values (comma separated).
Secondary Attribute Value	If the family group and sort order is defined for a secondary block, then this will be the list of all attribute values (comma separated).



Table 1-36 (Cont.) Family Group and Sort Order


Column	Description
Additional Secondary Attribute Value	If the family group and sort order is defined for an additional secondary block, then this will be the list of all attribute values (comma separated).

When you click the Add (or Edit) Product Family Group and Sort Order link, it opens a pop-up where you can specify the fixture type, block-level at which rule will be defined, and the sequence of attributes and order of attribute values.

## Family Group & Sorting Details Panel

Use this panel to examine the attributes and the sort order specified for the selected product family group and sort order. The sequence refers to the order in which attributes are applied. The sort order can be ascending (ASC), descending (DESC), or custom (CUSTOM). This defines how products are to be arranged, based on the order of attributes values. Custom indicates the order of the attribute values is determined by the user. For example, if a user wants to group first by brand and then by flavor, then brand would be assigned a sequence of 1 and flavor a sequence of 2. If there are three brands, Lindt, Hersheys and Cadburys, then ascending order is Cadburys, Hersheys and Lindt. This indicates to ASO that products are to be arranged first by brand and then by flavor and then, within brand, by the specified order.

Figure 1-50 Family Group and Sorting Details Panel




## **Inherited Locations**

This is used to add or remove inherited locations.



Figure 1-51 Inherited Locations



### **Planogram Constraints**

The Planogram Constraints tab, displays a list of optimization locations along with values for four constraints: Use Visual Guidelines, Use Product Spacing, Merge Adjacent Bays, and Set Usable Space.

Service levels can be defined at the planogram level using the Planogram Constraints screen.

You can edit these constraints by selecting the row or rows whose settings you want to change and then click **Edit Constraints**.

Use the drop-down menus to select a new setting. For Set Usable Space, you must enter a value between 1% and 100%. Select Do Not Change if you do not want to change a particular constraint. Click **Save** to save your changes.

**Table 1-37 Planogram Constraints** 

Column	Description
Space Cluster/Store	The name of the optimization location.
Parent Cluster	The name of the parent cluster for the optimization location.
Use Visual Guidelines	Indicates whether or not to use visual guidelines. Values are Yes and No.
Use Product Family Group	Indicates whether or not to use Product Family Group and Sort Order constraints. Values are Yes and No.
Use Product Spacing	Indicates whether or not to use product spacing. Values are Yes and No.
Merge Adjacent Bays	Indicates whether or not to merge adjacent bays. Values are Yes and No. The optimization process provides the option of merging adjacent bays.
Set Usable Space	A value between 1 and 100 that indicates the usable space. available to the optimization process. A values less than 100 forces the optimization process to leave some fixture space unused for aesthetic or other reasons.



### **Optimization Objectives**

The Optimization Objectives table, includes:

- Maximize Sales Units. This tells the optimization to fill the planogram with items that will
  result in best possible sales units for selected items/facings.
- Maximize Sales Revenue. For an item, sales revenue is calculated as price times the sales
  units. This tells the optimization to fill the planogram with items that will result in the best
  possible sales revenue for selected items/facings.
- Maximize Gross Profit. For an item, gross profit is obtained by multiplying the difference between price and cost, and sales units. This tells the optimization to fill the planogram with items that will result in the best possible gross profit for selected items/facings.
- Maximize Sales Revenue/On Hand Units. For each item, the ratio is calculated and added together. This objective tells the optimization to fill the planogram with items that result in the best possible revenue for the inventory units carried for each item.
- Maximize Gross Profit Return on Investment. This objective tells the optimization to fill the planogram with items that result in the best possible total profit, but that at the same time minimize the total inventory cost at the planogram-level. As one can imagine, carrying too much inventory will result in higher revenues or profits but at a higher cost of carrying more inventory. This metric lets the user strike a balance between these two metrics. There are two versions supported: the generic version in which the user is unable to provide the store-level inventory. To use the generic version GENERIC\_GMROI\_FLG is set to 'Y' in RSE CONFIG.
- Maximize Sales Units (Weighted). This objective is similar to 'Maximize Sales Units' except that here each item's contribution to objective is weighted by the IPI values provided by CMPO.
- Maximize Sales Revenue (Weighted). This objective is similar to 'Maximize Sales Revenue' except that here each item's contribution to objective is weighted by the IPI values provided by CMPO.
- Maximize Gross Profit (Weighted). This objective is similar to 'Maximize Gross Profit' except that here each item's contribution to objective is weighted by the IPI values provided by CMPO.
- Maximize Sales Revenue/On Hand Units (Weighted). This objective is similar to 'Maximize Sales Revenue/On Hand Units' except that here each item's contribution to objective is weighted by the IPI values provided by CMPO.
- Maximize Gross Profit Return on Investment (Weighted). This objective is similar to
  Maximize Gross Profit Return on Investment except that here each item's contribution to
  the objective (in the numerator and denominator) is weighted by the IPI values provided by
  CMPO.

Weighted objectives are weighed using the IPI values provided by CMPO.

Select one or more rows in order to modify specific objectives using the **Apply** button.

**Table 1-38 Optimization Objectives** 

Field	Description
Space Cluster/Store	The name of the optimization location.
Parent Cluster	The name of the parent cluster of the optimization location.
Optimization Objectives	The name of the current optimization objective.



### **Contextual Information**

Each of the five tabs within the Objectives and Constraints stage have associated contextual information. The information is displayed based on the selections you make in the location hierarchy table.

The Product Constraints information includes:

- Constraint Values, which displays a list of the constraints and associated metrics
- Constraint Charts, which provide a summary for each constraint
- Product Details

**Product Groups information includes:** 

- Product Group Summary, which displays counts for the group types
- Product Lookup, which shows, for a given product, the associated group ID, group name, and group type

Visual Guidelines information includes:

- Visual Guidelines Summary, which includes an Attributes histogram for each attribute, and Attributes Group histogram
- Attributes Lookup, which provides details about product counts for individual attributes
- Visual Guidelines Detail, which analyzes attribute values and product counts by sequence number

Planogram Constraints information includes:

- Constraint Charts, which provide summaries for each constraint
- Planogram Space, which can help you understand the relationship between the available space and the set of products.

Optimization Objectives information includes:

- Optimization Objectives
- Product Details, which includes details for IPI values, price, and margin percentage

# Results and Analysis

After the optimization run is complete, the results are displayed in the Results and Analysis stage. You can see summary performance data and view planograms for the optimization runs. In this stage, you can make a limited number of overrides to the table view or the planogram view. Substantive changes require that you re-configure settings and complete another optimization run.

The results are displayed in two tables. The upper table displays the total optimized performance. The data is summed for all the stores in a space cluster. You can access the virtual planogram by clicking the **View Planogram** icon. The lower table displays detailed results with product-level data. The data you see is the average for store numbers, not totals for space clusters.

You can drop products from the lower table for one or more locations; these dropped products are listed in a table.

Alerts are also provided, along with supporting metrics.



#### **Actions To Take**

From the Results and Analysis stage, you can:

- Revisit earlier stages in order to make changes to various settings and then re-submit the
  optimization. You can also validate a run in order to look for constraints that produce errors
  or warnings. See <u>Validation</u> for more details.
- Copy and save the run using the Save As functionality in the Action menu. Use the copy to make changes and then compare the results.
- Approve the run and make it available for assortment analysis.
- Leave the run in the optimization list without taking any actions. You cannot delete the run; you must be in Optimization List in order to delete a run.

# **Optimization Results**

The Optimization Results table is shown in Figure 1-52.

Figure 1-52 Optimization Results



You can toggle between a tree view and a table view to examine the results. The tree view displays the results hierarchically. The results are either a sum of lower level values, an average of lower level values, or a distinct count.

**Table 1-39 Optimization Results** 

Field	Description
Space Cluster/Store	The name of the optimization location: Store or Space Cluster.
Optimization Locations	The number of optimization locations.
Store Count	The number of distinct stores for a given level.
Planogram Length	A comma-separated list of selected planogram lengths
Total Lengths	The total count of planogram lengths for which the optimization was run. If more than one total is displayed, you can click the number to access a pop-up window. You can modify selected planogram lengths for the specified optimization location.
Available Products	A count of the available products for a given space cluster level.
Included Products	A count of the included products in an assortment for a given space cluster level.



Table 1-39 (Cont.) Optimization Results

Field	Description
Sales Units	The value for sales units in the optimization results. This value is aggregated at higher levels by summing the values for the lower levels.
Sales Value	The value for sales. This value is aggregated at higher levels by summing the values for the lower levels.
Margin Value	The value for margin. This value is aggregated at higher levels by summing the values for the lower levels.
Lost Sales Units	The value for lost sales units. This value is aggregated at higher levels by summing the values for the lower levels.
GMROI	This is the value of Gross Margin Return on Investment. This value is aggregated at higher levels by taking a ratio of the sum of margin at lower levels and sum of inventory cost at lower levels
Service Level	The value for the service level. The value is aggregated at higher levels by averaging the values for the lower levels.
Alerts	The number of alerts. This value is aggregated at higher levels by summing the values for the lower levels.
Overrides	The number of user overrides. This value is aggregated at higher levels by summing the values for the lower levels.

### **Included Products**


The Included Products table lists metrics at various levels of aggregation. You can select specific products from the table and click the **Delete** button in order to remove them from the results. You see a list of the products you want to delete and are prompted to confirm the action.

# **Dropped Products**

The Dropped Products table, shown in Figure 1-53, lists all the products that have been dropped per optimization process rules including but not limited to user override action or if the inclusion product constraint is set to Do Not Include. This panel functions like a simplified pivot table so you can pivot on the columns in the panel. In addition, you can also click on Export to Excel to export the list of dropped products.



Figure 1-53 Dropped Products



### **Alerts**

The Alerts table, in Figure 1-54, shows the metrics provided for alerts.

Figure 1-54 Alerts

		Used Space Percent	Dropped Products Percent	Dropped Products Count	Service Level Value	Service Level Units
Mainstream - Small - E (Northwest)	Dropped Percent, Dropped Count	96.7%	45.9%	28		1

The Used Space Percent can help you see if there is too much open space.

The Dropped Products Percent and Dropped Products Count can help you see if too many products were eliminated from an assortment.

The Service Level Value and Service Level Units can help you understand stockout levels.

You can configure the following parameters to control the thresholds for the alerts.

**Table 1-40 Alerts Parameters** 

Parameter Name	Description
ALRT_LESS_THAN_PCT_USED_SPACE	An alert will be triggered if the run optimization results use less space than the value specified by this global parameter.

Table 1-40 (Cont.) Alerts Parameters

Parameter Name	Description
ALRT_LESS_THAN_SERVICE_LEVEL_AMT	An alert will be triggered if the run optimization results have a sales service level lower than he value specified by this parameter.
ALRT_LESS_THAN_SERVICE_LEVEL_QTY	An alert will be triggered if the run optimization results have a quantity service level lower than he value specified by this parameter.
ALRT_MORE_THAN_CNT_PRODUCT_DROPPE D	An alert will be triggered if the run optimization results dropped more products than the value specified by this parameter.
ALRT_MORE_THAN_PCT_PRODUCT_DROPPE D	An alert will be triggered if the run optimization results dropped a percentage of product higher than he value specified by this parameter.

# **Contextual Information**


The Results and Analysis stage provides summary information about sales units, sales value, service level, and included products.

- Results Summary
- Inclusion Summary

# Planograms

When you click the **View Results** icon, you see a pop-up window displaying a planogram your run. Depending on your permissions, you can edit the planogram.

Figure 1-55 Planogram



### **Selection View**

Left-click a facing to highlight it.



#### **Fixture Details**

When you mouse over a fixture, the following information is displayed: fixture type, length, depth, and elevation.

#### **Product Details**

When you mouse over a product, the following information is displayed: product name, product code, facing count, facing ID, display style, main orientation, dimensions, stacking option, and elevation. When applicable, visual guideline information such as the attribute values used for the four levels of blocking are shown. Similarly, when applicable, the family group and sort order definition, such as the attributes used (in the order defined) and the attribute values (in the order defined) are shown.

### **Actions**

When you right-click a facing to select it, you have access to the following actions: editing facings, add, delete, move, save changes, cancel changes, and undo all changes.

Virtual Planogram for SC\_00001 with Length 192

Edit Facings
Add
Delete
Move
Save Changes
Undo all Overrides

Figure 1-56 Virtual Planogram with Action Menu

### **Edit Facings**

When you select this action, you can change the facing quantity.

### Delete

Use this action to delete a product. Deleted products can be added back using the Add Products action.

#### Add

When you select this action, you see a list of product codes for dropped products from which to choose. The product you select is restored to its original position and with the same number of facings as when it was dropped.



#### Move

If you move a product on a shelf, it moves to the 0 location on the shelf. For a facing move, the product is moved to the first available shelf location after the last product facing.

#### Save

The save action commits changes to the database.

#### Cancel

The cancel action rolls back any changes.

#### **Undo Overrides**

This action restores the planogram to the original results. If you close the application without saving changes, the next time you log in, you are prompted to save the changes.

### Historical Planograms

Click the **Compare to History** button to view a historical planogram. Such planograms cannot be modified.

The historical planogram contains colored rectangles representing products. You can change the color mapping in the historical planogram and select images of products (if available). To do this, click the **Color** button. You see the Color Mapping pop-up, from which you can choose one of the following color mappings:

- Product ID (the default)
- Product Image

### Capping


Capping is an alternative way of defining the top layer(s) of a product on a shelf after the bottom layer(s) has been placed. Capping layers may differ from the corresponding bottom layers, in both numbers of rows and columns as well as the individual dimensions. The VPOG pop-up displays the applicable capping layers. It also provides capping information in the hover pop-up. This only occurs when the style indicates capping, and it is applicable to the whole product display style, independent of the hover location. The following capping information is shown:

- Capping Facing Count. The horizontal facing count for the capping layer.
- Capping Height Facing Count. The depth facing count for the capping layer.
- Capping Depth Facing Count. The depth facing count for the capping layer.
- Capping Dimensions. Product dimensions for the corresponding capping layer.
- Capping Elevation. Elevation of the corresponding capping layer.
- Capping Orientation. Orientation of the corresponding capping layer.

Figure 1-57 provides an example of the VPOG hover pop-up.




Figure 1-57 VPOG Hover Pop-Up



### **Changing Color Mapping**

You can change the colors of the displayed boxes or display product images in the virtual planogram. To do this, **click** the **Color** button.

Figure 1-58 Color Button




You see the Color Mapping pop-up, from which you can choose the color mapping you want:

- Product ID (the default)
- Primary Attribute Value—The coloring of products (rectangle boxes) is based on the primary attribute values.




Figure 1-59 Primary Attribute Value



All Visual Guidelines—In this selection, the coloring is by the complete blocking criteria:
 Primary Attribute Value, Additional Primary Attribute Value, Secondary Attribute Value, and Additional Secondary Attribute Value. If you do not specify any level, it will display as null, as shown in Figure 1-60.

Figure 1-60 All Visual Guidelines



Product Image



Figure 1-61 Color Mapping Pop-Up



### Validation

You can validate your data and constraint settings within each stage of Execute Space Optimization by using the **Validate** option in the Action menu. Validation lets you identify problems with potential data or constraints prior to initiating a complete optimization run. The Validate functionality is enabled after you create a run, provide it with a name, and populate it with a POG set and a group of stores or clusters. The Validate functionality is disabled for a run once it has a status of Finalized or Approved.

The validation process provides you with a quick way to determine if an optimization problem has any obvious incorrect data or parameters before you submit a run and request an optimization result. The process is not designed to find all possible errors or warnings, as some infeasible scenarios are only identifiable by the optimization process itself. However, the validation does provide you with the opportunity to find potential issues, and to then navigate back to the Fixture and Product Data or Objective and Constraints stage in order to address the setup issues. This can help you avoid submitting a run for optimization and then discovering that changes are required.

The validation process checks on issues with price, cost, demand, and replenishment data. Specifically, it looks for invalid values, missing data and generates an error or warning, depending on whether the product is mandatory or optional. Except for replenishment data which can also be modified in the UI, other data issues will require the user to correct and reload the data interface files.

Validation identifies two types of conflict:

- Errors. Identifies data or constraints that prevent an optimization from completing successfully. You must correct all errors before you execute the run.
- Warnings. Identifies data or constraints that you may want to review and possibly change.
   Warnings do not necessarily cause the optimization to fail but can have unwanted consequences in terms of the results. Thus, it is always a good practice to review the warnings before clicking Submit.

Figure 1-62 Summary with Error





Figure 1-63 Summary with Warning



Figure 1-64 Error Details



# **Details About Errors and Warnings**

If the validation you request finds errors or warnings, you will see an error icon in the Summary area of the stage you are in. Some validation checks only apply to shelf fixtures while others apply to both shelves and pegboards. To view the details, expand the Validation Errors and Warning section below the Summary section. Click each link in order to display the Details for Validation Errors and Warnings dialog box, which contains information explaining the error or warning that can help you address the problem.

### Warnings

Warnings are informational and indicate that optional items will be handled according to the constraints you set. Here is a list of possible warnings and suggested optional actions to address the warnings.

Table 1-41 Warnings and Suggested Actions

Alert #	Warning Description	Suggested Optional Action
201	Optional product in all or nothing group becoming effective mandatory.	No fix needed.
202	Optional choose from product becoming effective mandatory.	No fix needed.
209	Optional product becoming effective drop.	No fix needed.
211	Optional product too wide.	Reduce the minimum number of facings or change the elevation or orientation.
212	Optional product too tall.	Change the elevation or orientation.
213	Optional product lacks shelf.	Change the elevation.
232	No common set of shelves.	Edit the group settings or elevation ranges.
236	No common facing value	Edit the group settings or facing ranges.



Table 1-41 (Cont.) Warnings and Suggested Actions

Alert #	Warning Description	Suggested Optional Action
1000	Product price is 0 or negative for (all) the store(s)	Optional: Re-load so_assort_proloc_pricecost_stg.txt file with valid prices otherwise the product will be dropped
1001	Product price is 0 or negative for some stores	Optional: Re-load so_assort_proloc_pricecost_stg.txt file with valid prices otherwise the product will be incorrectly valued/dropped as affected stores are discarded
1002	Product cost is 0 or negative for (all) the store(s)	Optional: Re-load so_assort_proloc_pricecost_stg.txt file with valid costs otherwise the product will be dropped
1003	Product cost is 0 or negative for some stores	Optional: Re-load so_assort_proloc_pricecost_stg.txt file with valid costs otherwise the product will be incorrectly valued as affected stores are discarded
1004	Product price and cost are equal for (all) the store(s)	Optional: Re-load so_assort_proloc_pricecost_stg.txt file with valid prices or costs otherwise the product will be dropped
1005	Product price and cost are equal for some stores	Optional: Re-load so_assort_proloc_pricecost_stg.txt file with valid prices or costs otherwise the product will be incorrectly valued/dropped as affected stores are discarded
1006	Product cost is greater than the price for (all) the store(s)	Optional: Re-load so_assort_proloc_pricecost_stg.txt file with valid prices or costs otherwise the product will be dropped
1007	Product cost is greater than the price for some stores	Optional: Re-load so_assort_proloc_pricecost_stg.txt file with valid prices or costs otherwise the product will be incorrectly valued/dropped as affected stores are discarded
1008	Product demand is 0 or negative for (all) the store(s)	Optional: Re-load so_assort_proloc_fcst_stg.txt file with valid demand values otherwise the product will be dropped
1009	Product demand is 0 or negative for some stores	Optional: Re-load so_assort_proloc_fcst_stg.txt file with valid demand values otherwise the product will be incorrectly valued/dropped as affected stores are discarded
1010	Missing price, cost, and demand data for (all) the store(s)	Optional: Re-load the so_assort_proloc_pricecost.txt and so_assort_proloc_fcst.txt files with valid data otherwise the product will be dropped



Table 1-41 (Cont.) Warnings and Suggested Actions

Alert #	Warning Description	Suggested Optional Action
1011	Missing price, cost, and demand data for some stores	Optional: Re-load the so_assort_proloc_pricecost.txt and so_assort_proloc_fcst.txt files with valid data otherwise the product will be incorrectly valued/dropped as affected stores are discarded
1012	IPI value is 0 or negative for (all) the store(s)	Optional: Re-load so_assort_product_strcltr_stg.txt with valid IPI values otherwise the product will be dropped
1013	IPI value is 0 or negative for some stores	Optional: Re-load so_assort_product_strcltr_stg.txt with valid IPI values otherwise the product will be incorrectly valued/dropped as affected stores are discarded
1014	Casepack value is 0 or negative for (all) the store(s)	Optional: Change casepack data through UI or by re-loading so_prod_loc_repl_param_stg.txt file with valid values otherwise product will be dropped
1015	Casepack value is 0 or negative for some stores	Optional: Change casepack data through UI or by re-loading so_prod_loc_repl_param_stg.txt file with valid values otherwise product will be dropped
1016	Product inventory cost is 0 or negative for (all) the store(s)	Optional: Re-load so_assort_proloc_pricecost_stg file with valid inventory cost otherwise the product may be incorrectly valued/dropped
1017	Product inventory cost is 0 or negative for some stores	Optional: Re-load so_assort_proloc_pricecost_stg file with valid inventory cost otherwise the product may be incorrectly valued/dropped as affected stores are discarded
1018	Product store inventory is 0 or negative for (all) the store(s)	Optional: Re-load so_assort_proloc_pricecost_stg file with valid inventory quantity otherwise the product may be incorrectly valued/dropped
1019	Product store inventory is 0 or negative for some stores	Optional: Re-load so_assort_proloc_pricecost_stg file with valid inventory quantity otherwise the product may be incorrectly valued/dropped as affected stores are discarded
1100	Mandatory product price is 0 or negative for (all) the store(s)	Re-load so_assort_proloc_pricecost_stg.txt file with valid prices otherwise the product will be dropped or make the product optional
1101	Mandatory product price is 0 or negative for some stores	Optional: Re-load so_assort_proloc_pricecost_stg.txt file with valid prices otherwise the product will be incorrectly valued/dropped as affected stores are discarded
1102	Mandatory product cost is 0 or negative for (all) the store(s)	Re-load so_assort_proloc_pricecost_stg.txt file with valid costs otherwise the product will be dropped or make the product optional



Table 1-41 (Cont.) Warnings and Suggested Actions

Alert #	Warning Description	Suggested Optional Action
1103	Mandatory product cost is 0 or negative for some stores	Optional: Re-load so_assort_proloc_pricecost_stg.txt file with valid costs otherwise the product will be incorrectly valued as affected stores are discarded
1104	Mandatory product price and cost are equal for (all) the store(s)	Re-load so_assort_proloc_pricecost_stg.txt file with valid prices or costs otherwise the product will be dropped or make the product optional
1105	Mandatory product price and cost are equal for some stores	Optional: Re-load so_assort_proloc_pricecost_stg.txt file with valid prices or costs otherwise the product will be incorrectly valued/dropped as affected stores are discarded
1106	Mandatory product cost is greater than the price for (all) the store(s)	Re-load so_assort_proloc_pricecost_stg.txt file with valid prices or costs otherwise the product will be dropped or make the product optional
1107	Mandatory product cost is greater than the price for some stores	Optional: Re-load so_assort_proloc_pricecost_stg.txt file with valid prices or costs otherwise the product will be incorrectly valued/dropped as affected stores are discarded
1108	Mandatory product demand is 0 or negative for (all) the store(s)	Re-load so_assort_proloc_fcst_stg.txt file with valid demand values otherwise the product will be dropped or make the product optional
1109	Mandatory product demand is 0 or negative for some stores	Optional: Re-load so_assort_proloc_fcst_stg.txt file with valid demand values otherwise the product will be incorrectly valued/dropped as affected stores are discarded
1110	Mandatory product missing price, cost, and demand data for (all) the store(s)	Re-load the so_assort_proloc_pricecost.txt and so_assort_proloc_fcst.txt files with valid data otherwise the product will be dropped or make the product optional
1111	Mandatory product missing price, cost, and demand data for some stores	Optional: Re-load the so_assort_proloc_pricecost.txt and so_assort_proloc_fcst.txt files with valid data otherwise the product will be incorrectly valued/dropped as affected stores are discarded
1112	Mandatory product's IPI value is 0 or negative for (all) the store(s)	Re-load so_assort_product_strcltr_stg.txt with valid IPI values otherwise the product will be dropped or make the product optional
1113	Mandatory product's IPI value is 0 or negative for some stores	Optional: Re-load so_assort_product_strcltr_stg.txt with valid IPI values otherwise the product will be incorrectly valued/dropped as affected stores are discarded



Table 1-41 (Cont.) Warnings and Suggested Actions

Alert #	Warning Description	Suggested Optional Action
1114	Mandatory product's casepack value is 0 or negative for (all) the store(s)	Change casepack data through UI or by reloading so_prod_loc_repl_param_stg.txt file with valid values otherwise product will be dropped or make the product optional
1115	Mandatory product's casepack value is 0 or negative for some stores	Optional: Change casepack data through UI or by re-loading so_prod_loc_repl_param_stg.txt file with valid values otherwise product will be incorrectly valued/dropped as affected stores are discarded
1116	Mandatory product inventory cost is 0 or negative for (all) the store(s)	Optional: Re-load so_assort_proloc_pricecost_stg file with valid inventory cost otherwise the product may be incorrectly valued
1117	Mandatory product inventory cost is 0 or negative for some stores	Optional: Re-load so_assort_proloc_pricecost_stg file with valid inventory cost otherwise the product will be incorrectly valued as affected stores are discarded
1118	Mandatory product store inventory is 0 or negative for (all) the store(s)	Optional: Re-load so_assort_proloc_pricecost_stg file with valid inventory quantity otherwise the product may be incorrectly valued
1119	Mandatory product store inventory is 0 or negative for some stores	Optional: Re-load so_assort_proloc_pricecost_stg file with valid inventory quantity otherwise the product will be incorrectly valued as affected stores are discarded

# **Correcting Errors**

Once you have made corrections to the errors, you must run Validate again in order to make sure that all the errors have been corrected. Here is a list of possible errors and recommended corrections.

Table 1-42 Errors and Recommended Solutions

Alert #	Error Description	Recommended Solution
101	Mandatory product too wide.	Reduce minimum number of facings, change product orientation, or make the product optional.
102	Mandatory product too tall.	Change the product orientation or make the product optional.
103	Mandatory product lacks shelf.	Change the elevation setting or make the product optional.
106	Mandatory products combined width too wide for shelf.	Reduce the minimum facings or make some of the products optional.
107	Mandatory products combined area too large for pegboard.	Reduce the minimum facings or make some of the products optional.
121	Choose from group lacking products.	Edit the group settings or add products.



Table 1-42 (Cont.) Errors and Recommended Solutions

Alert #	Error Description	Recommended Solution
122	Choose from group with too many products.	Edit the group settings or change the mandatory product inclusion settings.
127	Same shelf group lacks shelf.	Edit group settings or change the mandatory product elevation settings.
128	Same shelf group is too wide.	Edit the group settings or change the mandatory product elevation or inclusion settings.
129	Same shelf group is too tall.	Edit the group settings or change the mandatory product elevation or inclusion settings.
132	Match facing group without match.	Edit the group settings or change the mandatory product inclusion settings.

Once all errors are corrected, you can submit the optimization run.

# **Assortment Mapping**

The Assortment Mapping tab is used to view and edit the results of the automated mapping between assortments and planograms that the system performs.

# Assortment Mapping Interface

The Assortment Mapping interface is divided into two sections. The Select Assortment table lists all assortments with a status of either Ready for SO or POG Mapping Needs Review. When you first access this screen, it is pre-filtered to show only POG Mapping Needs Review assortments, with the QBE field for the Status column already filled in. To see the Ready for SO assortments, you must clear this field and click **Enter** to trigger the update.


The Assortment to Planogram Mapping table displays the planogram mappings for each combination of location and product in a given assortment. You must have the appropriate permissions to edit the assortments.

Use the **Save** Button to save and validate any edits you make. This updates the mappings and refreshes the mapping table display. You must save your changes for one assortment before editing another assortment.

### Select Assortment

The Select Assortment table, shown in <u>Figure 1-65</u>, displays a list of the assortments that require mapping. These assortments have a status of either Ready for SO or POG Mapping Needs Review. Use this list to select an assortment to edit.

Figure 1-65 Select Assortment





When you select an assortment to edit and click the **Edit** button, you see the Edit Status dialog box. You can toggle the status of the assortment between Ready for SO and POG Mapping Needs Review by using the radio buttons. These radio buttons are disabled if errors exist in the assortment mapping table.


**Table 1-43** Select Assortment

Field	Description	
ID	The ID of the assortment.	
Name	The name of the assortment.	
Last Updated By	The user ID of the person who last updated the assortment.	
Last Update	The date when the assortment was last updated.	
Location Level	The location level for the assortment (Store Cluster or Cluster Assortment).	
Product Category	The product category for the assortment.	
Status	The status of the assortment.	

### Assortment to Planogram Mapping

Once you select an assortment from the Select Assortment table, you see the components of that assortment (Figure 1-66). You can add a planogram mapping, delete a mapping, change the planogram node for the mapping (re-mapping), or edit the demand spread factor for the mapping.

Figure 1-66 Assortment to Planogram Mapping



#### **Adding Planogram**

Use the **Add Planogram** button to add a planogram mapping row that is similar to the mapping row you select. This action copies all the data from the original row with the exception of Node, Season, Demand Spread Factor, Store Count, Stores with Planograms, and Errors. You are presented with a dialog box in which you specify the planogram node. If you cancel out of the dialog box without selecting a node, the row you are adding is removed.

### **Deleting**

Use the Delete button to delete a mapping. If you try to delete the only mapping for a specific combination of location and product, you will see an error message.



#### Re-Mapping

Use the Re-map button to change the planogram node (displayed in the Node column) for the mapping. You see the Select Planogram Node dialog box. When you change this value, three other changes occur. The value for the planogram season (displayed in the Season column) is changed to the first available season for the node. The value for the demand spread factor is changed to 100 percent. The values for Store Count and Stores with Planograms are both changed to zero.

You cannot select a node that results in a duplicate mapping for a specific combination of location and product when the duplicate mapping is defined as a mapping that has the same location, product, and planogram node (regardless of planogram season).

### **Editing the Demand Spread Factor**

You can edit the demand spread factor within the Assortment to Planogram Mapping table. You must enter a number between 1% and 100%. For a set of mappings for the same combination of location and product, the total of the demand spread factors for the mappings cannot be greater than 100 percent. If the number exceeds this, you will see an error message after you click **Save** (which validates your edits).

### Tables for Stores and Clusters

The Assortment to Planogram Mapping tables for Stores and for Clusters are slightly different. The following two tables describe each table.

Table 1-44 Assortment to Planogram Mapping for Stores

Field	Description
Store Code	The store code.
Store	The name of the store.
Assortment Cluster	The name of the assortment cluster.
Product Code	The product code.
Product Name	The name of the product.
Planogram Hierarchy Remap	The button you use to select a new planogram node for the mapping.
Planogram Hierarchy Node	The planogram node, which is the sub-category level of the assortment product hierarchy that the mapping applies to.
Planogram Hierarchy Season	The season that the mapping applies to.
Demand Spread Factor	The amount of demand that should be allocated to the mapping (within a specific combination of location, product, node, and season.
Planogram Available	Y= planogram is available for a specific combination of location, product, planogram node, and planogram season. $N=$ not available.
Errors	The errors that occur during mapping.

Table 1-45 Assortment to Planogram Mapping for Clusters

Field	Description
Assortment Cluster	The name of the assortment cluster.
Product Name	The name of the product.



Table 1-45 (Cont.) Assortment to Planogram Mapping for Clusters

Field	Description
Demand Spread Factor	The amount of demand that should be allocated to the mapping (within a specific combination of location, product, node, and season.
Planogram Hierarchy Remap	The button you use to select a new planogram node for the mapping.
Planogram Hierarchy Node	The planogram node, which is the sub-category level of the assortment product hierarchy that the mapping applies to.
Planogram Hierarchy Season	The season the mapping applies to.
Store Count	The number of stores in the assortment cluster. This value is zero for mappings that are edited.
Stores With Planograms	The number of stores in the assortment cluster that have planograms for the selected planogram set, based on the planogram data that has been loaded. This value is zero for mappings that are edited.
Errors	The errors that occur during mapping.
Product Code	The product code.

### **Mapping Errors**

Three errors are identified by the mapping process.

- Total demand spread factor (DSF) out of range. Action: The value must not exceed a 100 percent the DSF within the mapping. Results must be adjusted to stay between 1% and 100%.
- Unmapped product. Action: There is no mapping information for a product. Add the
  mapping information and manually map the product or remove the product from the
  assortment feed.
- Unmapped store. Action: There is no POG available for the store. Add store information to the POG feed, remove the store from the assortment, or update the mapping information to map the assortment against a different POG Set with information for the store.

### (i) Note

After providing new data (with the exception of the assortment files), such as POGs, mapping data, and so on, that specifically provides a solution for the exceptions and errors found by the mapping process, the user must execute the Re-map action from the pull-down menu. This will trigger a new mapping process run for the assortment against the latest data available. The new data picked by the remapping process can clear the exceptions and errors found by the last mapping process and allow the assortment to move forward for optimization.

# **ASO Integration with Assortment Planning**

Assortment and Space Optimization Cloud Service (ASO) has several native integrations with the Assortment Planning (AP) application. ASO is used to determine the optimal selection and arrangement of products within stores by optimizing the product assortment and product placement on a virtual planogram. AP is used to create assortments for an assortment period



by store cluster level, that can be interfaced with ASO to send the approved assortments and it can receive back space optimized assortments from ASO as part of the final approval process.

# **ASO** Integration

Assortment Planning (AP) creates the initial assortment plan, and this plan is integrated with ASO for Assortment and Space Optimization. Once optimized, ASO plans are imported back into AP at the store level. Users review and manage exceptions and finalize assortment plans. If the delta between the AP initial plan and the ASO recommended plan is too high, the plan from AP will go through another round of optimization, and the recommendation is sent back to AP. AP will send the final assortment plan to ASO, which may share the plan with a space planning solution.

To enable this integration, ASO has exposed two web services for integration with AP. The first web service performs the export of data from AP to ASO. This web service accepts the following parameters:

Variable	Data Type	Required	Description
exportAssortmentReque stHeader	-	Y	This is the standard common request header.
requestID	String	Y	This is used mainly for tracking or troubleshooting. If in production, results for the request made must be investigated across two systems in case AIF and the callee system can both track. For now, logic is still not in place, so this is optional.
rspVersion	String	Y	RSPVersion is mainly for tracking which version the client is currently using. There can be case where AIF can implement another version and the client is not ready to adapt to the newer versions. So, versions can be v1, v2 and so on.
timeout	String	N	Timeout in case of webbooks isused mainly to indicate how long a client should wait for the request results before notifying the user that a certain request could not complete in time. This can be for many reasons. (Two systems can agree upon). Code is still not in place, so this is optional.



Variable	Data Type	Required	Description
assortSetId	VARCHAR2(80)	N	Assortment Set ID - If this is not provided, this will default to the Assortment ID (assorId).
assortId	VARCHAR2(80)	Υ	Assortment ID
assortLabel	VARCHAR2(80)	Υ	Assortment Label
requestType	NUMBER(2)	Y	Request Type. This field can accept two values. 1 - Optimization Request, 2 - Finalized Assortment Reporting.
assortLocType	NUMBER(2)	Y	Assortment Location Type. Indicates whether 1 – Cluster Level or 2 – Store Level. AP will send value. A value of 1 is the default.
prodLevel	VARCHAR2(80)	Y	Product level is CLS for Class and SBC for Sub-Class. The Product level used in the RAP interface for all integration. This is the Level Name in RSE Product Source External Reference table.
prodKey	VARCHAR2(80)	Y	Product ID. The Product ID used in the RAP interface for all integration. This is the Level ID in RSE Product Source External Reference table.
startWeek	DATE	Υ	EOW Date for Start Week. Format YYYYMMDD. For example, 20230101.
endWeek	DATE	Y	EOW Date for End Week. Format YYYYMMDD. For example, 20230101.
targetUnit	NUMBER(20,4)	N	MFP Target at Subclass/ Assort Period level. This will be used for future enhancements as requested, but currently, ASO does not consume this.
storeClusters	-	Y	Collection for Store Clusters. This is not required if requestType = 2 (Finalization Request).
storeClusterId	VARCHAR2(80)	Υ	Store Cluster to Store Mapping



Variable	Data Type	Required	Description
storeClusterName	VARCHAR2(80)	Y	Store Cluster Name. This is displayed all across the ASO UI and is a crucial value for doing runs/reviewing results.
storeId	VARCHAR2(80)	Y	List of Stores in Store Cluster. This is the loc_ext_key in RSE Location Source External Reference table.
items	-	Y	Collection for Items. This collection is not required if requestType = 2 (Finalization Request).
itemId	VARCHAR2(80)	Y	The Item ID. This is the prod_ext_key in RSE Product Source External Reference table.
phltem	VARCHAR2(1)	N	Place Holder Item Indicator. Indicates whether the given itemId is a Placeholder Item or not. Valid Values are Y and N.
phLikeltem	VARCHAR2(80)	N	Place Holder Like Item. Used by the system to generate a forecast. AP should plan on providing like items, as this will act as an override. Required if phltem is Y.
finalizedPhItem	VARCHAR2(80)	N	Finalized Place Holder Item. This is the external ID that is known and shared across applications. The finalized product key must be one of the known products also included within the assortment. Must equal to a prod_ext_key in RSE Product Source External Reference table.
itemAttributes	-	N	Collection for Place Holder Item Attributes.
phAttrName	VARCHAR2(50)	Y	Name of the product attribute that is being passed. Must match a known product attribute.



Variable	Data Type	Required	Description
phAttrValue	VARCHAR2(50)	Y	Specific value that must be used for the placeholder product/ attribute combination.
assortments	-	Y	Collection for Assortments at Item/ Store Cluster Level. This collection is not required if requestType = 2 (Finalization Request).
storeClusterId	VARCHAR2(80)	Y	Reference to storeClusterId in SO_ASSORTMENT_CL USTER.
assortedItem	NUMBER(2)	Y	Also known as Priority. 1 = Mandatory. 2 = Core. 3 = Optional.
assortedQty	NUMBER(18,4)	Y	This is the (average) end of week in-store inventory level of a product that includes shelf and backroom inventory.
unitPrice	NUMBER(18,4)	Y	Product price. Single currency unit determined at the configuration level. No multicurrency is allowed.
unitCost	NUMBER(18,4)	Y	Product cost. Single currency unit determined at the configuration level. No multicurrency is allowed.

### Note

IPI\_VALUE is not included in the JSON file, hence it defaults to 0.

The parameters listed above are sent in JSON format, are extracted in ASO, and inserted into staging tables. Data from the JSON format message will be validated in the staging tables. There is existing validation for each staging table that the data goes to before it is loaded to the main tables.

Here is the response from the first web service:

Key/Parameter	Required	Data Type	Comments
exportAssortmentRespo	Υ	Collection	



Key/Parameter	Required	Data Type	Comments
status	Y	String	200 - For Successful Processing of Data. (Data is accepted but business data validation are done in the background, check with Webservice 2 if any data validation error occurs.) 400 - For Validation failure in loading data into ASO. 500 - Referential
			Integrity Error.
statusMsg	N	String	Status Message for the status Code. For 500 this is null. See the target value on the messageResponse. The 500 error code response is coded using a common library so cannot be modified.
messageResponse	Υ	Collection	Response Message from ASO for error criteria.

### Example of the web service response:

### Sample 1: Successful Data Load Response

#### Sample 2: Reference Integrity Issue (status code 500)

#### Sample 3: Response with a Validation Error Encountered

Before the first web service is invoked, the forecast data must be set up and mapped to ASO. AP will not provided the forecast data for items, so a Forecast Run Type must be mapped to ASO manually during the initial forecast setup. If it is not set up, validation errors will be inserted into the Global Error Log table. The forecast setup must be at the SKU-STORE-WK level, and the forecast intersections must match exactly; this means the forecast levels in run type must be created at that level. You cannot have multiple run types that are Active and mapped to ASO; in case multiple are active at the same time, then the latest active and mapped ASO run type will be used. The forecast is expected to be generated weekly to coincide with AIF batches and other ASO data processing activities.



Aside from these integrations, you are still expected to provide all other required data feeds for ASO to function, including replenishment attributes by item and location, planograms, fixtures, display types, and orientations.

The loading and validation process is done in the background, as it may take some time; any validation errors will not be returned immediately by the loading web service. After an assortment has been successfully loaded using the first web service, the user can check the status of the assortment using the second web service. It is important to note that optimization runs are created manually in the AIF ASO Execute Space Optimization UI. When the run is set up, then the second web service can provide optimization details. The second web service returns the ASO Optimized Assortment details for a given assortment ID. If multiple runs are available, only the latest optimization run's detail will be returned. Although multiple assortments are supported, it is recommended that only a single or a few assortment IDs be provided, as this can affect the performance, depending on the size of the optimization result or the server connectivity.

If the optimization run is not available because the given assortment ID has some data errors, records from the AIF's ETL Assortment bad tables and the global validation log table will be returned. See the list of ASO ETL BAD tables above. The data business validation errors are not available immediately as the Webservice 1 is running in the background.

Here are some samples of global validations:

- Assortment product/location is missing forecast data.
- (Assortment) Product/location does not have replenishment data.
- Assortment cluster (cluster level assortment) has no products.
- Assortment is missing forecast data.
- Assortment product does not have a display style.

Optimization run details with the item IDs and store IDs expected by AP can be queried from the SO\_RUN\_OPT\_LOC\_POG\_PROD\_RES\_VW and SO\_RUN\_OPT\_LOC\_STORE\_DTL\_VW views.

In the UI, results can vary, depending on the Location Optimization Level. For Cluster Level, the details are based on the Space Cluster/Item ID, while for Store Level, the details are based on Store ID/Item ID.

The input for the second web service can either be a single assortment or multiple assortments.

#### Sample: Single Assortment

The response of the second web service contains the optimized assortment details for the given assortment ID. It also contains the data validation errors, if any.



Variable	Data Type	Required	Comments
getAssortmentDetailRes ponseHeader	Collection	Υ	This is the standard common response header.



Variable	Data Type	Required	Comments
responseCode	String	Y	This is the response code. Values can be any of the following  100 – All Assortment - Successful Return of Data  200 – All Assortment - Period Optimization Not Found  300 - All Assortment - Period Optimization Still In Progress.  500 – Integrity Error on Input The following are the response codes if the multiple Assortment IDs provided have varying status:  600 – Successful Return of Optimization Data for some assortments. No Optimization for some Assortment Periods.  700 - An Assortment may still be in Progress. Optimization data found for some assortments.  800 – Some Assortments Still in Progress, no optimization data found.  900 – Some Assortments Still in Progress, some have no data found. Some assortments Still in Progress, Some have no data found. Some assortments have optimization data found.



Variable	Data Type	Required	Comments
responseCodeMessage	String	Y	Response Code Messages for the Response Code above. For 500 code error, check messageResponse for details. Integrity errors will show each item.
messageResponse	Collection	N	This will return only JSON validation error messages.
soOptResultDetail	Collection	N	Collection for the optimization details.
			Members:
			statusCode String
			statusCode String Message
			assortmentl String d
			runStatus String
			locationOpti String mizationLev el
			assortment String Status
			soOptimizat Collection ionResult
			soSanityCh Collection eckResult
			soRejected Collection DataErrors



Variable	Data Type	Required	Comments
statusCode	String	Y	Status Code for the given assortment's Optimization run, if any.  100 – Assortment Space Optimization - Successful Return of Data  200 – Assortment Space Optimization Not Found  300 - Assortment Space Optimization Still In Progress. Run is still in progress if the run status is of the following:
			1 Initial Setu ized p in Progr ess
			2 Not Setu Start p in ed Progr ess
			3 Build Setu Opti p in mizat Progr ion ess Locat ions
			4 Opti Setu mizat p in ion Progr Locat ess ion Acce pted
			6 Proc Runn essin ing g
			11 Sub Sub mitte mitte d d
			12 Valid Valid ating ating
statusCodeMessage	String	Y	The Status Code Message for the Status Code above.
assortmentId	String	Y	Assortment ID (External Assortment ID for AIF). Added to make a distinction as multiple assortments maybe provided in Input JSON.



Variable	Data Type	Required	Comments
runStatus	String	N	Optimization Run status if available. i.e., Completed, Approved, Submitted etc. From SO_RUN_HDR.RUN_ST ATUS_ID and SO_RUN_STATUS.DES CR
locationOptimizationLeve	String	N	Location Optimization Level.
assortmentStatus	String	N	Assortment Status Will be provided only if there are Data validation issues in Assortment.
soOptimizationResult	Collection	N	Collection for the Optimization Result.Queried from the SO_RUN_OPT_LOC_P OG_PROD_RES_VW view. Members:
			itemId storeId spaceClusterId spaceClusterLabel avgSlsQty avgSlsAmt avgGrossProfit avgGrossProfitPercent
			Note: Not all columns in the SO_RUN_OPT_LOC_P OG_PROD_RES_VW view are provided. Only included are what the AP requires, based on their original design with the inclusion of the avgGrossProfitPercent.



Variable	Data Type	Required	Comments
soSanityCheckResult	Collection	N	Collection of Optimization Run's Validation Warnings and Errors.Query is from the SO_RUN_SANITY_CHE CK_RES_VW view. Members:
			error details resolution conflictType prodGrpId runOptClusterId runOptClusterName parentRunOptClusterId parentRunOptClusterNa me
			pogLength
error	String	Υ	Error Type. Valid values are Error or Warning.
resolution	String	Υ	Suggested Resolution for the Warning or Error.
conflictType	String	Υ	Conflict Detail.
prodGrpld	String	Υ	Product ID where the issue occurred.
runOptClusterId	BigDecimal	Υ	Run Optimization Cluster ID.
runOptClusterName	String	Υ	Run Optimization Cluster Name.
parentRunOptClusterId	BigDecimal	Υ	Run Optimization Parent Cluster ID.
parentRunOptClusterNa me	String	Υ	Run Optimization Parent Cluster Name.
pogLength	BigDecimal	Υ	Planogram Length detail.
details	String	Υ	Details of the Warning or the Error.
resolution	String	Υ	Suggested Resolution for the Warning or Error.
conflictType	String	Υ	Conflict Detail.
prodGrpld	String	Υ	Product ID where the issue occurred.
runOptClusterId	BigDecimal	Υ	Run Optimization Cluster ID.
runOptClusterName	String	Υ	Run Optimization Cluster Name.
parentRunOptClusterId	BigDecimal	Υ	Run Optimization Parent Cluster ID.
parentRunOptClusterNa me	String	Υ	Run Optimization Parent Cluster Name.



Variable	Data Type	Required	Comments
pogLength	String	Υ	Planogram Length detail.
soRejectedDataErrors	Collection	N	Collection of Assortment Rejected Data Error. Queried from the SO ETL BAD tables (see list above) and the SO_GLOBAL_VALDT_E RROR_LOG table. • errorMessage • keyDetail
errorMessage	String	Υ	Error Message.
keyDetail	String	Y	Key Detail. This shows the Assortment ID or Assortment Set ID where the error occurred.



# Appendix: Oracle Retail AI Foundation Cloud Services Overview

Oracle Retail AI Foundation Cloud Services provides advanced analytical insights to drive the end-to-end retail process. The foundation provides out-of-the-box analytics that are purpose built for end business users with a workflow and a user experience. The foundation also provides the ability to create a retailer's own AI/ML models and then invoke and infuse those results into the business process as well as create application extensions with Oracle's Application Express.

For information about the Control and Tactical Center, see the latest AIF User Guide on the Oracle Help Center.

Oracle Retail AI Foundation Cloud Services includes the features described below.

**Advanced Clustering** utilizes machine learning techniques to cluster stores based upon similar selling patterns, providing a more customer-centric set of clusters to drive assortment decisions. The capability also provides the ability to cluster based upon other metrics and attributes such as space to drive assortment space optimization.

**Customer Segmentation** provides the ability to utilize historical performance, customer loyalty information, and demographics to segment customers to utilize in downstream processes.

**Attribute Extraction** automates the attribution process by extracting attributes from product descriptions.

**Customer Decision Trees** provide the ability to understand exactly how your customer is shopping their assortment. Are they coming in for a specific brand, product, size? This then enables you to utilize these insights within planning as dynamic attributes to pivot from your static merchandise hierarchy to analyze your assortment decisions in the way in which your customer is shopping.

**Demand Transference** drives insights into the overall uniqueness of items and the potential demand transferable to other items which is then utilized in assortment recommendations for both assortment planning as well as space optimization.

**Profile Science** helps retailers understand how to break their buys by size, looking at not just historical sales but also where there were stock outs and missed opportunities.

**Affinity Analysis** identifies associations across products and product types such as halo and cannibalization. These insights can help drive the overall decisioning of process of promotion planning and impact analysis.

**Innovation Workbench** enables data scientists to create their own AI/ML models with open source programming language as well as SQI.

Each of these capabilities can further fuel data-driven decisions for retailers.