

Oracle® Real User Experience Insight

Installation Guide

Release 5.0 for Linux x86-64

E12487-08

April 2009

Oracle Real User Experience Insight Installation Guide, Release 5.0 for Linux x86-64

E12487-08

Copyright © 2009 Oracle and/or its affiliates. All rights reserved.

Primary Author: Paul Coghlan

Contributing Author: Eddy Vervest

The Programs (which include both the software and documentation) contain proprietary information; they are provided under a license agreement containing restrictions on use and disclosure and are also protected by copyright, patent, and other intellectual and industrial property laws. Reverse engineering, disassembly, or decompilation of the Programs, except to the extent required to obtain interoperability with other independently created software or as specified by law, is prohibited.

The information contained in this document is subject to change without notice. If you find any problems in the documentation, please report them to us in writing. This document is not warranted to be error-free. Except as may be expressly permitted in your license agreement for these Programs, no part of these Programs may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose.

If the Programs are delivered to the United States Government or anyone licensing or using the Programs on behalf of the United States Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the Programs, including documentation and technical data, shall be subject to the licensing restrictions set forth in the applicable Oracle license agreement, and, to the extent applicable, the additional rights set forth in FAR 52.227-19, Commercial Computer Software--Restricted Rights (June 1987). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

The Programs are not intended for use in any nuclear, aviation, mass transit, medical, or other inherently dangerous applications. It shall be the licensee's responsibility to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of such applications if the Programs are used for such purposes, and we disclaim liability for any damages caused by such use of the Programs.

Oracle, JD Edwards, PeopleSoft, and Siebel are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

The Programs may provide links to Web sites and access to content, products, and services from third parties. Oracle is not responsible for the availability of, or any content provided on, third-party Web sites. You bear all risks associated with the use of such content. If you choose to purchase any products or services from a third party, the relationship is directly between you and the third party. Oracle is not responsible for: (a) the quality of third-party products or services; or (b) fulfilling any of the terms of the agreement with the third party, including delivery of products or services and warranty obligations related to purchased products or services. Oracle is not responsible for any loss or damage of any sort that you may incur from dealing with any third party.

Contents

Preface	vii
Audience	vii
Documentation Accessibility	viii
Related Documents	viii
Conventions	viii
1 Getting Started	
1.1 What is RUEI?	1-1
1.1.1 Data Collection	1-1
1.1.2 Product Architecture	1-2
1.2 Security	1-2
1.3 Connection Options	1-3
1.3.1 Copy Ports	1-3
1.3.2 TAPs	1-4
1.4 Installation and Deployment Options	1-5
1.4.1 Scalability Options	1-6
1.5 Hardware Requirements	1-7
1.5.1 Single-Server Requirements	1-7
1.5.2 Reporter Requirements	1-7
1.5.3 Collector Requirements	1-8
1.6 Software Requirements	1-8
1.7 Network Requirements	1-9
1.8 Client Requirements	1-9
1.9 Overview	1-9
2 Installing the Linux Operating System	
2.1 Introduction	2-1
2.2 Download ISO Image and Burn DVD	2-1
2.3 Run Installer	2-1
2.4 Set up Disk Partitioning	2-2
2.5 Network Configuration	2-3
2.6 Package Installation	2-3
2.7 Post-Installation Wizard	2-4
2.8 Create Additional Users and Reboot	2-7
2.9 Verify NTP Daemon Operation	2-8

3 Installing the Required Components

3.1	Installing the Operating System Prerequisites	3-1
3.1.1	Installing All Requirements Using a Yum Repository (Optional).....	3-2
3.2	Installing and Configuring the Oracle Database.....	3-3
3.2.1	Creating the Database User Accounts and Groups	3-3
3.2.2	Configuring the Kernel Parameter Settings.....	3-3
3.2.3	Setting Shell Limits for the Oracle User	3-4
3.2.4	Creating the Database Directory	3-4
3.2.5	Configuring the Oracle User's Environment.....	3-5
3.2.6	Creating an Oracle init Script File	3-7
3.2.7	Setting the Memory Usage	3-7

4 Installing the RUEI Software

4.1	Obtaining the RUEI Software.....	4-1
4.2	Installing the Apache Web Server and PHP	4-1
4.2.1	PHP Configuration	4-1
4.2.2	Avoiding rsvg Warnings	4-2
4.3	Unpacking the RUEI Software	4-2
4.4	Installing the Oracle Database Instant Client	4-2
4.5	Installing the php-oci8 Module.....	4-2
4.6	Installing the Zend Optimizer.....	4-3
4.7	Installation of the RUEI Software	4-3
4.8	Configuring the Network Interface.....	4-4
4.9	Enabling Multibyte Fonts (Optional, but Recommended)	4-4
4.10	Mail (MTA) Configuration (Optional, Reporter Only).....	4-5
4.11	SNMP (Optional, Reporter Only)	4-5
4.12	Configuring Automatic Browser Redirection (Optional)	4-5
4.13	Configuring Reporter Communication (Split-Server Setup Only)	4-5
4.14	Verifying Successful Installation of RUEI	4-6
4.15	Upgrading From RUEI 4.5.x to 5.0	4-6
4.15.1	Differences Between 4.5.x and 5.0	4-9
4.15.2	Rolling back an Upgrade	4-10

5 Configuring RUEI

5.1	Introduction	5-1
5.2	Performing Initial RUEI Configuration	5-1
5.3	Configuring a Collector System.....	5-5
5.3.1	Resetting a Collector System.....	5-5
5.4	Performing Post-Installation Configuration	5-6
5.4.1	Specifying the Cookie Technology	5-6
5.4.2	Adding/Uploading HTTP SSL Keys	5-6
5.4.3	Specifying How Users are Identified	5-6
5.4.4	Naming Pages	5-6
5.4.5	Specifying the Scope of Monitoring.....	5-6
5.4.6	Authorizing Initial Users	5-7
5.5	Verifying and Evaluating Your Configuration.....	5-7

5.5.1	Viewing a Traffic Summary	5-7
5.5.2	Confirming Data Collection	5-8

A Troubleshooting

A.1	The prepare_uxinsight_db.sh Script Fails	A-1
A.2	The Applying Settings Dialog Hangs	A-1
A.3	Starting Problems	A-2
A.4	Data Collection Problems	A-2
A.5	Data Processing Problems	A-3
A.6	E-Mail Problems	A-3
A.7	SSL Decryption Problems	A-4
A.8	Missing Packages and Fonts Error Messages	A-4
A.9	ORA-xxxxx Errors	A-5
A.10	Oracle DataBase Not Running	A-5
A.11	General (Non-Specific) Problems	A-6
A.12	Network Interface Not Up	A-6

B Installation Checklist

C Third-Party Licenses

Index

Preface

Oracle Real User Experience Insight (RUEI) provides you with powerful analysis of your network and business infrastructure. You can monitor the real-user experience, define Key Performance Indicators (KPIs) and Service Level Agreements (SLAs), and trigger alert notifications for incidents that violate them.

Audience

This document is intended for the following people:

- System administrators responsible for the installation of RUEI. This assumes a sound understanding of the Linux operating system.
- The person within your organization designated as the RUEI Administrator. This person is responsible for post-installation configuration, and system maintenance.

Some familiarity with network and Web technology is assumed. In particular, you should have a sound understanding of network topology, and a good operational knowledge of your organization's network and application environment.

This guide is organized as follows:

- [Chapter 1, "Getting Started"](#) introduces RUEI. In particular, how it monitors data traffic, the role of the Reporter and Collector modules, and the supported configurations.
- [Chapter 2, "Installing the Linux Operating System"](#) describes the procedure for installing the base operating system.
- [Chapter 3, "Installing the Required Components"](#) describes the procedure for installing all the components required by RUEI.
- [Chapter 4, "Installing the RUEI Software"](#) describes the procedure for preparing the server system(s) for RUEI, and installing the RUEI software. The procedure for upgrading an existing RUEI 4.5.x installation to release 5.0 is also explained.
- [Chapter 5, "Configuring RUEI"](#) describes the procedure for initially configuring RUEI. This procedure is performed by the person within the organization who has been assigned the role of RUEI Administrator.
- [Appendix A, "Troubleshooting"](#) highlights the most common issues encountered when installing RUEI, and offers solutions to quickly locate and correct them. It should be reviewed before contacting Customer Service.
- [Appendix B, "Installation Checklist"](#) provides a checklist of actions that should be completed, and the information gathered, before starting to install the RUEI software.

- [Appendix C, "Third-Party Licenses"](#) contains licensing information about certain third-party products included with RUEI.

Documentation Accessibility

Our goal is to make Oracle products, services, and supporting documentation accessible to all users, including users that are disabled. To that end, our documentation includes features that make information available to users of assistive technology. This documentation is available in HTML format, and contains markup to facilitate access by the disabled community. Accessibility standards will continue to evolve over time, and Oracle is actively engaged with other market-leading technology vendors to address technical obstacles so that our documentation can be accessible to all of our customers. For more information, visit the Oracle Accessibility Program Web site at <http://www.oracle.com/accessibility/>.

Accessibility of Code Examples in Documentation

Screen readers may not always correctly read the code examples in this document. The conventions for writing code require that closing braces should appear on an otherwise empty line; however, some screen readers may not always read a line of text that consists solely of a bracket or brace.

Accessibility of Links to External Web Sites in Documentation

This documentation may contain links to Web sites of other companies or organizations that Oracle does not own or control. Oracle neither evaluates nor makes any representations regarding the accessibility of these Web sites.

Deaf/Hard of Hearing Access to Oracle Support Services

To reach Oracle Support Services, use a telecommunications relay service (TRS) to call Oracle Support at 1.800.223.1711. An Oracle Support Services engineer will handle technical issues and provide customer support according to the Oracle service request process. Information about TRS is available at <http://www.fcc.gov/cgb/consumerfacts/trs.html>, and a list of phone numbers is available at <http://www.fcc.gov/cgb/dro/trsphonebk.html>.

Related Documents

For more information, see the following documents in the Oracle Real User Experience Insight library:

- *Oracle Real User Experience Insight User's Guide.*
- *Oracle Real User Experience Insight Accelerator for Oracle E-Business Suite Guide.*
- *Oracle Real User Experience Insight Accelerator for Siebel Guide.*
- *Oracle Real User Experience Insight Accelerator for PeopleSoft.*

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.

Convention	Meaning
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Getting Started

This chapter introduces the role of Oracle Real User Experience Insight (or RUEI for short), its architecture, attachment, and deployment options.


1.1 What is RUEI?

The usage of Web applications and services continues to grow. This includes not only the use of the Internet as a marketing channel, but also Extranet-based supply chain and back-office integration, and Intranet deployment of internal applications. Increasingly, it also includes the utilization of Web services which implement clearly defined business functions. RUEI is designed for measuring, analyzing, and improving the availability and performance of all of these deployment scenarios.

1.1.1 Data Collection

Typically, RUEI is installed before the Web servers, behind a firewall in the DMZ (as shown in [Figure 1-1](#)). The data collection method is based on Network Protocol Analysis (NPA) technology. This method is 100% non-intrusive. Hence, it does not place any load on a Web server, or require installing software agents that will impact performance. In addition, it does not require any change to the current application or infrastructure. When a new application release is deployed, or when an additional Web server is added, there is no or very little change required to RUEI's monitoring environment.

Figure 1-1 How RUEI Collects Data




When an object is requested by a visitor, RUEI sees the request and measures the time the Web server requires to present the visitor with the requested object. At this point, RUEI knows who requested the page (the client IP), which object was requested, and from which server the object was requested (server IP).

When the Web server responds and sends the requested object to the visitor, RUEI sees that response. At this point, RUEI can see whether there is a response from the server, whether this response is correct, how much time the Web server required to generate the requested object, and the size of the object. In addition, RUEI can also see whether the object was completely received by the visitor, or if the visitor aborted the download (that is, proof of delivery). Hence, RUEI can determine the time taken for the object to traverse the Internet to the visitor, and calculate the Internet throughput between the visitor and the server (that is, the connection speed of the visitor).

1.1.2 Product Architecture

RUEI is based on a three-layer product architecture, as shown in [Figure 1-2](#):

Figure 1-2 RUEI Product Architecture



The monitored data packets are processed by the following layers:

- **Data collection**
This layer is responsible for acquiring raw data and delivering it to the Data processor. This data can be collected from multiple sources. The available attachment options are described later in this section.
- **Data processing**
This layer converts the raw data into OLAP data sets. These comprise the multidimensional data structure that is viewable within the data browser.
- **Data presentation (reporter)**
This layer is RUEI's analysis and reporting environment. This is a Web-based information portal that can be accessed from any selected browser. The interface between the data processing and data presentation layer is based on open db calls.

1.2 Security

To read HTTP(S) data streams, a proprietary software module reassembles TCP/IP packet streams. Because the data collectors do not have an assigned IP number, and the software using these data collectors does not have a functional IP stack, RUEI is not able to respond to incoming traffic received on the data collectors. This makes RUEI "invisible" to the monitored networks, and completely secure.

Note: Because of the non-intrusive way in which RUEI collects data, it is not possible for it to request retransmission in the event of an error on the measurement port.

Data collection can be configured to log encrypted data. To facilitate this, a copy of the Web server's private SSL keys needs to be set up in the data collector. In addition, RUEI can be configured to omit logging of sensitive data in the arguments of POST requests of forms or content; so called *data masking* (or blinding).

1.3 Connection Options

RUEI supports the use of both copy ports¹ and TAPs² for monitoring network traffic. Copy ports and TAPs are available for copper or fibre-based network infrastructures. While both devices allow non-intrusive monitoring of network traffic, there are differences between these two connection options. These are highlighted in the rest of this section.

1.3.1 Copy Ports


A copy port is a switch that starts to build up a Layer 2 forwarding table on the basis of the source MAC address of the different packets that the switch receives. After this forwarding table is built, the switch forward traffic that is destined for a MAC address directly to the corresponding port.

For example, after the Web server MAC in [Figure 1-3](#) is learned, unicast traffic from the browser to the Web server is only forwarded to the Web server port. Therefore, the Collector does not see this traffic.

¹ Copy ports are also known as Switched Port Analyzer (SPAN) ports which is a feature of Cisco switches.

² Test Access Port (TAP) devices are provided by specialist vendors, such as NetOptics Inc.

Figure 1–3 Network Connection Using a Copy Port




In the configuration shown in the lower part of [Figure 1–3](#), the Collector is attached to a port that is configured to receive a copy of every packet that the browser sends. This port is called a copy port. Copy ports can copy traffic from any or all data ports to a single unused port and prevents bi-directional traffic on the port to protect against backflow or traffic into the network.

Be aware that activating a copy port on a switch can have a performance impact. Typically, copy ports support a wide range of configuration options, and for further information about these options you should consult your switch documentation or contact the vendor.

1.3.2 TAPs

TAPs can be placed between any two network devices (such as routers and firewalls). Any monitoring device connected to a TAP receives the same traffic as if it were in-line, including all errors. This is achieved through the TAP duplicating all traffic on the link, and forwarding it to the monitoring port(s). The example shown in [Figure 1–4](#) illustrates a typical TAP deployment for one Collector.

Figure 1–4 Network Monitoring Using a TAP



Unlike copy ports, in the event of power failure, TAPs continue to allow data to flow between network devices. TAP devices are available for copper or fibre-based infrastructures. Generally, the use of TAPs is considered preferable since they can be easily deployed when and where required, but engineers do need to re-cable a network link.

Note: Broadly speaking, there are three types of TAPs: network, regeneration, and aggregation TAPs. RUEI supports the use of network and regeneration TAPs. The use of aggregation TAPs is *not* supported. However, the deployment of multiple Collectors, or the connection of multiple links directly to one Collector, is available for the aggregation of data from multiple streams. In addition, be aware that when capturing data with a network-tap device, the use of cascaded tap configurations is not supported.

1.4 Installation and Deployment Options

A RUEI system can be configured in two different ways: as a Reporter, or as a Collector. Each installation option is reviewed in the following sections.


- **Reporter**

This is the standard installation option, and is the simplest to install and configure. Here, the Reporter provides a browser-based interface to the collected data. Note that each Reporter installation also contains a local Collector instance. The Reporter can either be configured to just process information gathered by this local Collector (this is a single-server configuration similar to the one shown in [Figure 1–5](#)), or can (optionally) be configured to receive information from additional Collector installations.

- **Collector**

If a RUEI system is installed as a Collector, it submits the data it gathers to a Reporter system. Multiple Collectors can be attached to the same Reporter. Configuration #1 in Figure 1–5 is an example of a single Collector split-server configuration, while Configuration #2 is an example of a split-server configuration using two Collectors. Note that a direct network connection is required between the Collector(s) systems and the Reporter system.

Figure 1–5 Configuration Options



1.4.1 Scalability Options

The use of multiple Collectors may be considered when there is a need to monitor very high levels of data traffic. In addition, this deployment also provides the possibility of enhanced security. For example, by placing the Collector(s) outside the office network, while placing the Reporter system within the network.

Split-server configuration #1 in Figure 1–5 shows an example of a typical DMZ installation. The Collector is located in the DMZ, and the Reporter is within the server network environment. Note that the local Collector instance is disabled. Split-server configuration #2 shows an example of a deployment consisting of two Collectors. This could, for example, be used between two data centers (both monitoring the DMZ), where one data center acts as a failover for the other.

Split-server configuration #3 shows an example of a deployment in which both data lines are monitored in the same reporting environment. Note that this deployment assumes that the traffic on each line is mutually exclusive. It also shows an example of a deployment used for security reasons. While the traffic from Web servers A and B are monitored and reported, the traffic from Web server C is not. This is also the reason why the Collectors are not placed above the switch.

For security reasons, it is recommended that access to the Reporter system is restricted to trusted IP ranges. Similarly, you may want to locate the Reporter system inside the internal network to maximize its security. The Collector's data gathering ports should be in the DMZ.

1.5 Hardware Requirements

The required minimum system specifications for the selected configuration (as explained in [Section 1.4](#)) are described in the following sections.

Network Cards

It is recommended that you carefully consider the selection of network cards for your infrastructure. Depending on the connection option you selected in [Section 1.3](#), "[Connection Options](#)", both copper and fibre-based network cards may be required. If necessary, consult both your network and systems management teams.

Note: For more information about required and recommended system specifications, please contact Customer Support.

1.5.1 Single-Server Requirements

Table 1–1 Single-Server System Requirements

Element	Requirements
CPU	64-bit Intel or AMD dual-CPU, dual-core processor (> 2 G Hz) or equivalent.
Memory	16 GB.
Disk space	Minimum 400 GB HDD free space. ^{1,2}
Network interfaces	When using a network-tap device ³ , a minimum of three network interfaces is required: <ul style="list-style-type: none"> ■ Two interfaces for network traffic capturing. ■ One interface for network services.
GSM modem (optional)	Optional support for a GSM modem to send text messages messages. The modem needs to be either GSM07.05 or GSM07.07 compatible. It can be connected through a serial or USB port. If USB is used, RUEI uses the first available port (ttyUSB0). Alternative methods of sending text messages are available (http/e-mail).

¹ To ensure acceptable performance of the RUEI installation, it is recommended to use high performance disk systems, with a minimum supported I/O rate of 70 MB/s. When monitoring high volumes of traffic, more powerful disk systems may be required. (Hardware) RAID-5, RAID-10, or equivalent storage configurations are strongly recommended.

² This may be need to be increased if Enriched data exchange is enabled.

³ When capturing data with a network-tap device, the use of cascaded tap configurations is not supported.

1.5.2 Reporter Requirements

Table 1–2 Reporter System Requirements

Element	Requirements
CPU	64-bit Intel or AMD dual-CPU, dual-core processor (> 2 G Hz) or equivalent.
Memory	16 GB.
Disk space	Minimum 400 GB HDD free space ^{1,2} .
Network interfaces	A minimum of 1 network interface is required.

Table 1–2 (Cont.) Reporter System Requirements

Element	Requirements
GSM modem (optional)	Optional support for a GSM modem to send text messages. The modem needs to be either GSM07.05 or GSM07.07 compatible. It can be connected through a serial or USB port. If USB is used, RUEI uses the first available port (ttyUSB0). Alternative methods of sending text messages are available (http/e-mail).

¹ To ensure acceptable performance of the RUEI installation, it is recommended to use high performance disk systems, with a minimum supported I/O rate of 70 MB/s. When monitoring high volumes of traffic, more powerful disk systems may be required. (Hardware) RAID-5, RAID-10, or equivalent storage configurations are strongly recommended.

² This may be need to be increased if Enriched data exchange is enabled.

1.5.3 Collector Requirements

The requirements for Collector systems are shown in [Table 1–3](#):

Table 1–3 Collector System Requirements

Element	Requirement
CPU	64-bit Intel or AMD dual-core processor or equivalent.
Memory	8 GB.
Disk space	Minimum 200 GB HDD free space.
Network interfaces	When using a network-tap ¹ device, a minimum of three network interfaces are required: <ul style="list-style-type: none"> ■ Two interfaces for network traffic capturing². ■ One interface for communication with the Reporter system. When using a network-copy port, a minimum of two network interfaces are required: <ul style="list-style-type: none"> ■ One interface for network traffic capturing. ■ One interface for communication with the Reporter system.

¹ Capturing data with a network-tap device prevents the use of a cascaded taps configuration.

² For up and down stream traffic. Note that the use of taps that integrate up and down stream traffic on one line is not recommended.

Important: Please note that an Intel (or compatible) 64-bit platform is a *strict* requirement for both the hardware and the operating system in all deployment scenarios.

1.6 Software Requirements

The following GNU/Linux distributions are supported:

- Oracle Enterprise Linux 5.x.
- RedHat Enterprise Linux 5.x.

Encrypting Sensitive Data

If sensitive data needs to be encrypted, you have the opportunity to encrypt your entire disk configuration during the disk partitioning phase of the Enterprise Linux installation procedure. For more information, see [Section 2.4, "Set up Disk Partitioning"](#).

1.7 Network Requirements

- All server system clocks should be synchronized via NTP using UDP port 123.
- Support DNS information requests over TCP and UDP port 53.
- Support reports and e-mail alerts using TCP port 25.
- Support SNMP traps on request from an SNMP Manager using UDP port 161/162.
- The RUEI user interface is accessible over HTTPS port 443.
- Each remote Collector system should be accessible by the Reporter system over port 22. It is recommended all other ports be blocked.

1.8 Client Requirements

The workstations that will access the RUEI user interface must have one of the following browsers installed:

- Mozilla Firefox 2.0 or 3.0.
- Internet Explorer 6 SP2.
- Internet Explorer 7.

Note that Javascript must be enabled. No other plug-ins are required.

In addition, the workstation should have a screen resolution of 1024 * 768 (or higher).

Important: Ensure that any pop-up blocker within the browser has been disabled.

AJAX Support

RUEI uses AJAX to enhance its user interaction. Internet Explorer relies on the MSXML control to facilitate AJAX. The AJAX dependencies can trigger a security warning when using strict security settings.

Internet Explorer 6 does not properly support transparent images in the PNG format. RUEI uses a well know fix (AlphaImageLoader) for this problem which relies on DirectX. If you are experiencing browser crashes with IE6, you may need to update your version of DirectX. The PNG fix can trigger a security warning when using strict security settings.

1.9 Overview

The process of preparing the server system, and installing the RUEI offtware, has the following phases:

1. Install the Linux operating system. This is described in [Chapter 2, "Installing the Linux Operating System"](#).
2. Install all prerequisites for RUEI. This is described in [Chapter 3, "Installing the Required Components"](#).
3. Install the RUEI software. This is described in [Chapter 4, "Installing the RUEI Software"](#). The procedure for upgrading an existing 4.5.x installation to release 5.0 is also described.
4. Perform an initial configuration of the RUEI installation. This is described in [Chapter 5, "Configuring RUEI"](#).

Installing the Linux Operating System

This chapter describes the procedure for installing Oracle Enterprise Linux 5.3. However, the procedure for installing RedHat Enterprise Linux 5.3 is virtually identical.

2.1 Introduction

The procedure for installing Oracle Enterprise Linux 5.3 is fully described in the product documentation. This section presents a summary of that procedure, and assumes a sound knowledge of Linux administration.

For information on vendor-specific variations, consult the appropriate documentation. The installation procedure described is based on the use of a DVD media package.

Obtaining the Linux Operating System

The Oracle Enterprise Linux 5.3 software is available from the Oracle E-Delivery Web site (<http://edelivery.oracle.com/linux>).

2.2 Download ISO Image and Burn DVD

1. Download the appropriate ISO image. This guide assumes you are using the DVD version of Oracle Enterprise Linux 5.3.
2. Unzip the files.
3. Burn the ISO file to DVD. Note that this requires the use of a DVD-burning utility (such as UltraISO or Magic ISO Maker).

Note: According to your corporate policy, the Linux installation procedure may use a different procedure to that described in the following sections.

2.3 Run Installer

Note: After installing Linux on the first node, repeat the Linux installation procedure for each system.

1. Ensure that server system is able to boot from DVD. Insert the Oracle Enterprise Linux DVD, and power on.

2. When the Oracle Enterprise Linux boot screen appears, press **Enter** to start the installation process.
3. When asked to test the DVD media, select **Skip**. After a short interval, the installer goes into GUI mode. (The media test is not necessary because the DVD burning software would have informed you of any errors on the media).
4. At the Welcome to Oracle Enterprise Linux screen, click **Next**.
5. Select the appropriate options from the Language and Keyboard settings screens.
6. If the installer detects a previous version of Enterprise Linux, you are prompted to "Install Enterprise Linux" or "Upgrade an existing installation". Select "Install Enterprise Linux", and click **Next**.

Important: Oracle recommends that you install the Linux operating system with the default software packages (RPMs), and that you do not customize the RPMs during installation. This installation includes most required packages, and helps you limit manual checks of package dependencies.

2.4 Set up Disk Partitioning

1. When prompted, select the default **Remove Linux partitions on selected drives and create default layout** option, and check the option **Review and modify partitioning layout**. When prompted to confirm your selection, select **Yes**. Click **Next** to continue.

Note: A check box allows you to encrypt the entire system. If selected, for security reasons, a password is required during booting the system.

2. When prompted to confirm the removal of all partitions, click **Yes**.
3. Review and modify (if necessary) the automatically selected disk partitions.

For most automatic layouts, the installer assigns 100 MB for `/boot`, 2 GB for swap, and the remainder is assigned to the root (`/`) partition. Ensure the specified SWAP space is sufficient. See [Table 2-1](#) and [Table 2-2](#) for required disk space and swap space requirements.

The installer creates a disk configuration using the Logical Volume Manager (LVM). For example, it will partition the first hard drive (`/dev/sda` in the described configuration) into two partitions: one for the `/boot` partition (`/dev/sda1`), and the remainder of the disk dedicated to a LVM named `VolGroup00` (`/dev/sda2`). The LVM Volume Group (`VolGroup00`) is then partitioned into two LVM partitions: one for the root file system (`/`), and another for swap. If you have selected a non-standard layout, ensure that the system meets the required disk space specifications shown in [Table 2-1](#). Ensure enough swap space is allocated for Oracle Enterprise Linux. Its required swap space is shown in [Table 2-2](#).

Table 2-1 Required Disk Space Specifications

Partition	Minimum Required Disk Space (GB)
<code>/u01/app</code> ¹	300

Table 2–1 (Cont.) Required Disk Space Specifications

Partition	Minimum Required Disk Space (GB)
/opt/ruei	0.5
/var/opt/ruei/	100

¹ This is the example location of the database used throughout this guide.

Table 2–2 Required Swap Space

Available RAM	Swap Space Required
Up to 8192 MB	Equal to the size of RAM.
More than 8192 MB	0.75 times the size of RAM.

Important: The Reporter server requires high performance data storage. RAID-10 or RAID-5 (or equivalent) storage configurations with high performance disks are strongly recommended.

Note: The requirements shown in [Table 2–1](#) and [Table 2–2](#) can vary depending upon the composition and volume of monitored data. For more information, please contact Customer Support.

4. Accept the GRUB boot loader, as well as all default values, and click **Next**.


2.5 Network Configuration

1. Ensure that a static IP address is assigned to the interface used to access the RUEI Web interface. In addition, the assigned IP address should be configured in the `/etc/hosts` file. If necessary, ensure that all Reporter and Collector systems are correctly defined in the DNS system.
2. Ensure that the network interface(s) used for network packet monitoring are administratively *up*, but *without* an IP address.

Important: Make the network interface *up* status permanent (after a reboot) by setting the ONBOOT parameter of the capturing interfaces to *yes*. The network interfaces configuration can be found in `/etc/sysconfig/networking/devices/ifcfg-ethX` (where *X* represents the necessary network interface). Alternatively, use the graphical utility **system-config-network** to perform the above actions.

2.6 Package Installation

1. Select the appropriate time zone for your environment, and click **Next**.
2. Specify a root password, and click **Next**.
3. At the additional tasks dialog box shown in [Figure 2–1](#), leave the **Customize later** radio button checked, leave all the check boxes unchecked, and click **Next**.

Figure 2–1 Additional Tasks Dialog Box

4. At the **About to install** screen, click **Continue** to start the installation.
5. At the prompt screen, click **Next** to begin installation of Enterprise Linux.
6. Upon successful installation, remove the DVD, and click **Reboot**.

Important: It is *strongly* recommended that you use the settings described above, and do not perform a "minimal" installation of Oracle Enterprise Linux. This can lead to a wide range of problems, further described in [Section A.8, "Missing Packages and Fonts Error Messages"](#).

2.7 Post-Installation Wizard

1. When the system boots for the first time, a post-installation wizard appears, and allows you to finalize the operating system configuration settings. Click **Forward**.
2. At the User license agreement screen, read the license terms. You will not be able to proceed until you have accepted them. Then click **Forward**.
3. Use the screen shown in [Figure 2–2](#) to allow only secure WWW (HTTPs) and SSH traffic. Be aware that, by default, SSH traffic is enabled, but secure WWW (HTTPS) traffic is not. Note that, when prompted with a warning about not setting the firewall, click **Yes**.

Figure 2–2 Firewall Configuration




4. Use the screen shown in [Figure 2–3](#) to disable Security Enhanced Linux (SELinux). Click **Forward**. Note that you are prompted with a warning that changing the SELinux setting requires rebooting the system so that the entire system can be relabeled. Click **Yes**.

Figure 2–3 SELinux Configuration

Important: Security Enhanced Linux (SELinux) must be disabled for correct operation of RUEI.

5. Accept the default setting on the Kdump screen (disabled), and click **Forward**.
6. Adjust the date and time settings using the screen shown in [Figure 2–4](#). The use of NTP is strongly recommended, and is required in a split-server deployment. Click **OK**.

Figure 2–4 Date and Time Settings



2.8 Create Additional Users and Reboot

1. Create any additional required (non-Oracle) operating system user accounts. Note that during the installation of the RUEI software, the `moniforce` user account is created. The creation of the `oracle` user is described in a later section. Do *not* create either user account at this point.
2. If prompted, confirm the detection of a sound card.
3. On the Additional CDs screen, click **Finish**.
4. Because the SELinux option has been changed (to disabled), you are prompted to reboot the system. Click **OK**.
5. After reboot, use the `root` user account, and the password you specified during installation to logon.

Text Mode Installation (Optional): When using the text mode installation, by default:

- Firewall: HTTPS (TCP 443) is blocked.
- Security: SE Linux is enabled.

Allow HTTPS traffic (TCP 443) and disable SELinux using the `system-config-securitylevel` utility.

2.9 Verify NTP Daemon Operation

Because the NTP daemon is a critical component of RUEI, especially in a split Reporter-Collector configuration, it is recommended that you verify that it is activated in at least run level 5 during boot. Use the following commands:

```
chkconfig --list | grep ntp
ntp      0:off  1:off  2:off  3:off  4:off  5:off  6:off
chkconfig ntpd on
chkconfig --list | grep ntp
ntp      0:off  1:off  2:on   3:on   4:on   5:on   6:off
/etc/init.d/ntpd start
Starting ntpd:                                [ OK ]
```

Note that if the NTP daemon is not already running, you can start it with the command

```
/etc/init.d/ntpd restart
```

The following sample output show when the NTP daemon is synchronized (indicated by an "*").

```
ntpq -pn
      remote           refid      st t when poll reach  delay  offset  jitter
=====
*194.171.167.130      .PPS.          1 u 994 1024 377   6.429  0.041  0.093
+80.85.129.25        130.235.20.3  3 u 725 1024 377   4.435  0.673  0.129
+82.94.235.106      135.81.191.59 2 u 678 1024 377   1.709  1.774  0.020
127.127.1.0         .LOCL.         10 l 8    64 377    0.000  0.000  0.001
```

Installing the Required Components

This chapter describes the procedure for installing all required components prior to installing RUEI. The installation of the RUEI software itself is described in [Chapter 4, "Installing the RUEI Software"](#).

Note: It is assumed throughout this guide that the installation is performed as the `root` user, unless indicated otherwise.

3.1 Installing the Operating System Prerequisites

1. If the Enterprise Linux DVD is mounted automatically, the content is located in the directory `/media/Enterprise Linux dvd 20090127` (the date depends on the downloaded version of the DVD). If the DVD is not automatically mounted, use the following commands to mount it:

```
mkdir -p /mnt/dvd
mount /dev/dvd /mnt/dvd
```

Note: In the rest of this chapter it is assumed the Linux operating system DVD is mounted on `/mnt/dvd`.

2. Install all prerequisites for the Oracle database using the following commands:

```
cd /mnt/dvd/Server
rpm -Uhv kernel-headers-2.6.18-128.el5.x86_64.rpm \
elfutils-libelf-devel-0.137-3.el5.x86_64.rpm \
elfutils-libelf-devel-static-0.137-3.el5.x86_64.rpm \
glibc-devel-2.5-* \
glibc-headers-2.5-34.x86_64.rpm \
gcc-4.1.2-44.el5.x86_64.rpm \
gcc-c++-4.1.2-44.el5.x86_64.rpm \
libstdc++-devel-4.1.2-44.el5.x86_64.rpm \
libgomp-4.3.2-7.el5.x86_64.rpm \
libaio-devel-0.3.106-3.2.x86_64.rpm \
sysstat-7.0.2-3.el5.x86_64.rpm
```

3. Issue the following command to install all prerequisites for the Apache Web server and PHP:

```
rpm -Uhv httpd-2.2.3-22.0.1.el5.x86_64.rpm \
apr-1.2.7-11.x86_64.rpm \
apr-util-1.2.7-7.el5.x86_64.rpm \
php-5.1.6-23.el5.x86_64.rpm \
```

```
mod_ssl-2.2.3-22.0.1.el5.x86_64.rpm \
distcache-1.4.5-14.1.x86_64.rpm \
php-common-5.1.6-23.el5.x86_64.rpm \
php-cli-5.1.6-23.el5.x86_64.rpm \
php-mbstring-5.1.6-23.el5.x86_64.rpm \
php-gd-5.1.6-23.el5.x86_64.rpm \
php-ldap-5.1.6-23.el5.x86_64.rpm \
gmp-4.1.4-10.el5.x86_64.rpm \
postgresql-libs-8.1.11-1.el5_1.1.x86_64.rpm
```

4. Issue the following command to install all prerequisites for the SNMP and mail components. Note this step is optional, and only relevant to Reporter installations.

```
rpm -Uhv sendmail-cf-8.13.8-2.el5.x86_64.rpm \
lm_sensors-2.10.7-4.el5.x86_64.rpm \
net-snmp-5.3.2.2-5.el5.x86_64.rpm \
net-snmp-utils-5.3.2.2-5.el5.x86_64.rpm
```

5. Issue the following the commands to install all optional fonts. Alternatively, install the multi-byte character sets necessary to meet your NLS requirements.

```
rpm -Uhv fonts-*
```

6. Continue with the rest of the installation procedure from [Section 3.2.1, "Creating the Database User Accounts and Groups"](#).

3.1.1 Installing All Requirements Using a Yum Repository (Optional)

As an alternative to manual installation, you can use a Yum repository to install the required RPMs. This requires a working Yum repository. For information on Yum repositories, see <http://linux.duke.edu/projects/yum/>. Install the necessary Oracle packages using the following commands:

```
yum -y install gcc
yum -y install gcc-c++
yum -y install compat-libstdc++-33
yum -y install libstdc++-devel
yum -y install elfutils-libelf-devel
yum -y install glibc-devel
yum -y install libaio-devel
yum -y install sysstat
```

Install the necessary RUEI packages using the following commands:

```
yum -y install perl-URI
yum -y install net-snmp
yum -y install sendmail-cf
yum -y install httpd
yum -y install mod_ssl
yum -y install php
yum -y install php-gd
yum -y install php-mbstring
yum -y install php-ldap
yum -y install bitstream-vera-fonts
yum -y install librsvg2
yum -y install xorg-x11-xinit
yum -y install fonts-*
```

3.2 Installing and Configuring the Oracle Database

This section describes the procedure for installing the Oracle database.

Download Oracle Database 11g Release 1 (11.1.0.6.0) Standard Edition, Standard Edition One, and Enterprise Edition from the Oracle database home page (<http://www.oracle.com/technology/software/products/database/index.html>).

The procedure for installing the Oracle database is fully described in the product documentation. This section presents a summary of that procedure.

The information in this guide is based on the *Oracle Database 11g for Linux x86-64 Quick Installation Guide*. It is recommended that you download and review it. It is available at http://download.oracle.com/docs/cd/B28359_01/install.111/b32285/toc.htm.

Note: The Oracle database's maximum memory usage is set by the `MEMORY_TARGET` parameter. By default, this is set to 40% of the available server RAM. For example, in a system with 16 GB RAM, it is set to approximately 6.4 GB. Note that if extra RAM is added to the server system to increase performance, it is not made available to the Oracle database until the `MEMORY_TARGET` parameter is manually increased.

Information about automatic memory management is available at http://download.oracle.com/docs/cd/B28359_01/server.111/b28310/memory003.htm#ADMIN11200.

3.2.1 Creating the Database User Accounts and Groups

1. Create two groups (`dba` and `oinstall`) with the following commands:

```
/usr/sbin/groupadd dba
/usr/sbin/groupadd oinstall
```

2. Create the `oracle` user, and specify `oinstall` as the primary group and `dba` as the secondary group, with the following command:

```
/usr/sbin/useradd -g oinstall -G dba oracle
```

3. Set the `oracle` user password with the following command:

```
passwd oracle
```

3.2.2 Configuring the Kernel Parameter Settings

1. Modify the `/etc/sysctl.conf` file to satisfy the Oracle installer's requirements by adding the following lines:

```
kernel.sem = 250 32000 100 128
net.ipv4.ip_local_port_range = 1024 65000
net.core.rmem_default = 4194304
net.core.rmem_max = 4194304
net.core.wmem_default = 262144
net.core.wmem_max = 262144
fs.file-max = 6553600
```

2. Make these changes effective immediately with the following command:

```
/sbin/sysctl -p
```

3.2.3 Setting Shell Limits for the Oracle User

1. To improve the performance of the software, you must increase the shell limits for the oracle user. Add the following lines to the `/etc/security/limits.conf` file:

```
oracle soft nproc 2047
oracle hard nproc 16384
oracle soft nofile 1024
oracle hard nofile 65536
```

2. If not already present, add the following lines to the `/etc/pam.d/login` file:

```
session required /lib64/security/pam_limits.so
session required pam_limits.so
```

3. Depending on the oracle user's default shell, you need to make changes to it. For the Bourne, Bash, or Korn shell, add the following lines to the bottom of the `/etc/profile` file:

```
if [ $USER = "oracle" ]; then
    if [ $SHELL = "/bin/ksh" ]; then
        ulimit -p 16384
        ulimit -n 65536
    else
        ulimit -u 16384 -n 65536
    fi
fi
```

For information about other shells, you should refer to the *Oracle Database 11g Release 1 for Linux x86-64 Quick Installation Guide* (at http://download.oracle.com/docs/cd/B28359_01/install.111/b32285/toc.htm).

3.2.4 Creating the Database Directory

Throughout this guide it is assumed that the directory `/u01/app` is the root of the Oracle installation. This is specified in the `ORACLE_BASE` environment variable.

1. Enter the following command to display information about all mounted file systems:

```
df -k
```

This command displays information about all the file systems mounted on the system, including:

- The physical device name
 - The total amount, used amount, and available amount of disk space
 - The mount point directory for that file system
2. Create the necessary subdirectories in the mount point directory that you identified and set the appropriate owner, group, and permissions for them using commands similar to the following:

```
mkdir -p /u01/app
chown -R oracle:oinstall /u01/app
chmod -R 775 /u01/app
```

3.2.5 Configuring the Oracle User's Environment

1. Logon to the system as the oracle user.
2. Add or edit the umask setting in the `~/ .bash_profile` file to the following:



```
umask 022
```
3. Make the setting active for the current shell by issuing the following command:


```
.. ./ .bash_profile
```
4. Set the ORACLE_BASE environment variable to define the location of the root of the Oracle directory tree:


```
export ORACLE_BASE=/u01/app/oracle
```
5. Unzip the Oracle database installation zip file. This creates the directory database. Then, run the graphical installer (note this will not run under user root). Ensure that your X Window environment is properly set up. In addition, when logging on remotely with SSH, ensure X forwarding is enabled. Use the following commands:


```
cd <location of the zip file>
unzip linux_11gR1_database.zip
./database/runInstaller
```
6. Use the installation wizard, and specify the values shown in [Figure 3-1](#).


Figure 3-1 Select Installation Method



Note that the **Create Starter Database** check box should be unchecked.

7. When ready, click **Next**. Specify the values shown in [Figure 3-2](#). When ready, click **Next**.

Figure 3–2 Specify Inventory Directory and Credentials




Important: Any warnings or errors reported during database installation (especially any missing prerequisites) must be resolved before proceeding. See [Section 3.1.1, "Installing All Requirements Using a Yum Repository \(Optional\)"](#) and [Appendix A, "Troubleshooting"](#) for information about required components.

If all dependencies are met, you can click **Next**.

8. When installation is almost complete, you are prompted to run two scripts, `oraInstRoot.sh` and `root.sh`, as `root`. This is shown in [Figure 3–3](#).

Figure 3–3 Configuration Scripts



Run the two scripts indicated in [Figure 3–3](#). They should be run in a terminal window as `root`. You will receive output similar to the following:

```
/u01/app/oraInventory/orainstRoot.sh
Changing permissions of /u01/app/oraInventory to 770.
Changing groupname of /u01/app/oraInventory to oinstall.
The execution of the script is complete

Finished product-specific root actions.
```

The second script generates the following output:

```
/u01/app/oracle/product/11.1.0/db_1/root.sh
Running Oracle 11g root.sh script...

The following environment variables are set as:
    ORACLE_OWNER= oracle
    ORACLE_HOME=  /u01/app/oracle/product/11.1.0/db_1

Enter the full pathname of the local bin directory: [/usr/local/bin]:
    Copying dbhome to /usr/local/bin ...
    Copying oraenv to /usr/local/bin ...
    Copying coraenv to /usr/local/bin ...

Creating /etc/oratab file...
Entries will be added to the /etc/oratab file as needed by
Database Configuration Assistant when a database is created
Finished running generic part of root.sh script.
Now product-specific root actions will be performed.
```

On completion of each script, return the dialog shown in [Figure 3–3](#), and click **OK**. In the main installer screen, verify that the message "The installation of Oracle database 11g was successful" appears. Click **Exit**, and confirm by clicking **Yes**.

3.2.6 Creating an Oracle init Script File

1. Logon as the root user.
2. Create an `/etc/init.d/oracledb` script file to start and stop the Oracle database. An example of this initialization script is available in the RUEI installation zip file (`/root/RUEI/50/oracledb`) explained in [Chapter 4, "Installing the RUEI Software"](#). Note that you will need to modify the settings for the `ORACLE_BASE` and `ORACLE_HOME` environment variables shown above if you selected a different installation directory for the Oracle database.
3. Make the script file executable and use it to start the Oracle database with the following commands:

```
chmod +x /etc/init.d/oracledb
/sbin/chkconfig --add oracledb
/sbin/service oracledb start
```

The Oracle database should now be up and running.

3.2.7 Setting the Memory Usage

For each Collector only system, set the available memory usage for the Oracle database to 10%. For example, if the system has 8 GB memory, then set the amount available to the Oracle database to 800 MB. To do so, issue the following commands as the `oracle` user:

```
$ sqlplus / as sysdba
SQL> alter system set memory_target=800M scope=both;
```

Note if you receive an error message stating the specified value is greater than MEMORY_MAX_TARGET, then the MEMORY_TARGET parameter has already been decreased.

Note that for Report systems, the default available memory usage setting does not need to be modified.

Installing the RUEI Software

This chapter describes the procedure for installing the Apache Web server and RUEI software. The procedure for upgrading an existing RUEI 4.5.x installation to release 5.0 is also described. The post-installation configuration procedure is described in [Chapter 5, "Configuring RUEI"](#).

4.1 Obtaining the RUEI Software

The RUEI software is available from the Oracle E-Delivery Web site (<http://edelivery.oracle.com>). Select the following media pack criteria:

- Oracle Enterprise Manager
- Linux x86-64

4.2 Installing the Apache Web Server and PHP

This section describes the installation and configuration of the Apache Web server, and the components that use it.

4.2.1 PHP Configuration

1. Ensure that the Web server starts automatically after re-boot by issuing the following command:

```
/sbin/chkconfig httpd on
```

2. Edit or create the `/etc/ruei.conf` file to contain the following lines:

```
export JAVA_HOME=/u01/app/oracle/product/11.1.0/db_1/jdk/jre
export INSTANTCLIENT_DIR=/usr/lib/oracle/11.1/client64
#
# Do not change the information below.
#
export TNS_ADMIN=/var/opt/ruei
#
export PATH=${INSTANTCLIENT_DIR}/bin:${PATH}
export LD_LIBRARY_PATH=${LD_LIBRARY_PATH}:${INSTANTCLIENT_DIR}/lib
export LD_LIBRARY_PATH=${LD_LIBRARY_PATH}:${JAVA_HOME}/lib/amd64
export LD_LIBRARY_PATH=${LD_LIBRARY_PATH}:${JAVA_HOME}/lib/amd64/server
```

An example of this file is included in the RUEI distribution pack. Note if the Oracle database has been installed to a different location than that specified in the `JAVA_HOME` setting, you should specify the required location. Ensure that the file is readable by the `moniforce` user by issuing the following command:

```
chmod 644 /etc/ruei.conf
```

3. Edit the `/etc/sysconfig/httpd` file to include the following line at the bottom of the file:

```
source /etc/ruei.conf
```

4. Create the following settings in the `/etc/php.d/ruei.ini` file:

```
session.gc_maxlifetime = 14400
memory_limit = 96M
upload_max_filesize = 128M
post_max_size = 128M
```

4.2.2 Avoiding rsvg Warnings

RUEI uses rsvg for graph generation. In order to avoid warnings about a missing directory, create the empty `.gnome2` directory using the following command:

```
mkdir -p /var/www/.gnome2
```

4.3 Unpacking the RUEI Software

Copy the downloaded RUEI zip file to `/root` directory on the server, and unzip it. Use the following commands:

```
cd /root
unzip package_name.zip
```

The following directories are created which contain the software needed to complete the RUEI installation:

- `/root/RUEI/50`
- `/root/RUEI/ZendOptimizer`
- `/root/RUEI/IC`
- `/root/RUEI/PHP`

4.4 Installing the Oracle Database Instant Client

Install the Oracle database Instant Client and SQLplus extension with the following commands as the `root` user:

```
cd /root/RUEI/IC
rpm -Uhv oracle-instantclient11.1-basic-*.rpm
rpm -Uhv oracle-instantclient11.1-sqlplus-*.rpm
```

4.5 Installing the php-oci8 Module

Install the `php-oci8` module (this is part of the RUEI distribution set) using the following commands:

```
cd /root/RUEI/PHP
rpm -Uhv php-oci8-11gR1-*
```

4.6 Installing the Zend Optimizer

Go to the directory containing the Zend Optimizer code, unpack the tar file, and run the Zend optimizer installer. Read the license agreement. You will not be able to proceed until you have accepted the license terms. Accept all default settings, and allow the installer to restart the Apache Web server. Issue the following commands:

```
cd /root/RUEI/ZendOptimizer
tar zxvf ZendOptimizer-3.3.3-linux-glibc23-x86_64.tar.gz
cd ZendOptimizer-3.3.3-linux-glibc23-x86_64
./install
```

Note: If you upgrade your system packages (for example, using Yum), this can overwrite changes you previously made to the `/etc/php.ini` file. Therefore, you should be prepared to re-install the Zend Optimizer. When doing so, ensure the Zend Optimizer installer indicates the location of the `php.ini` file as `/etc/php.ini` and not `/usr/local/Zend/etc/php.ini`.

4.7 Installation of the RUEI Software

1. The RUEI file and directory locations are fixed. Therefore, it is necessary to use the exact directory name described below. Create the RUEI application root directory using the following command:

```
mkdir -p /opt/ruei
```

2. Create the `moniforce` group and user. The home directory of `moniforce` should be set to `/var/opt/ruei`, with read permissions for group members.

```
/usr/sbin/groupadd moniforce
/usr/sbin/useradd moniforce -g moniforce -d /var/opt/ruei
chmod -R 750 /var/opt/ruei
chown -R moniforce:moniforce /var/opt/ruei
```

3. Make the `apache` and `moniforce` members of two additional groups using the following commands:

```
/usr/sbin/usermod -aG moniforce apache
/usr/sbin/usermod -aG uucp apache
/usr/sbin/usermod -aG uucp moniforce
```

4. Set the `ORACLE_HOME` environment variable. This is mandatory for preparation of the Oracle database. Issue the following command:

```
export ORACLE_HOME=/u01/app/oracle/product/11.1.0/db_1
```

5. Run the `ruei-prepare-db.sh` script as `root`. This script performs various environment and hardware checks, creates the `ux` database, and is located in the `/root/RUEI/50` directory. Password credentials for connecting to the database are stored in an Oracle wallet. The script prompts you for the RUEI database user password, and the password used to protect the wallet. Once the wallet password is stored in a secure location, the RUEI application can login to the database automatically. The default location of the wallet files are `cwallet.sso` and `ewallet.p12` in the `/var/opt/ruei` directory. Make the script executable and run it using the following commands:

```
cd /root/RUEI/50
chmod +x ruei-prepare-db.sh ruei-check.sh
```

```
./ruei-prepare-db.sh
```

The script prompts you for the intended deployment type. Enter `reporter`, `collector`, or `both`, depending on the planned deployment.

6. Add the following lines to the `/etc/profile` file to make the Oracle database known to RUEI:

```
ORACLE_SID=ux
export ORACLE_SID
```

7. Go to the directory which holds the RUEI software, and install the RUEI RPM packages with the following commands:

```
cd /root/RUEI/50
rpm -Uhv ux-*
```

8. Re-start the Apache Web server using the following command:

```
/sbin/service httpd restart
```

9. Verify the Oracle database is up and running by changing to the `moniforce` user and obtaining an SQL*Plus prompt with the following commands:

```
su - moniforce
sqlplus /@uxinsight
```

10. As the `moniforce` user, set the RUEI Administration password to enable logging onto the RUEI interface with the following commands:

```
su - moniforce
set-admin-password
```

You are prompted to enter and confirm the password.

Note: When defining the Administrator password, bear the following in mind:

- The password must have at least eight characters, and contain at least one non-alphanumeric character (such as \$, @, &, and !).
 - The initial password must be changed within seven days.
 - The user name and password are case sensitive.
-
-

4.8 Configuring the Network Interface

Make the monitoring network interface *up* status permanent (after a reboot) by setting the `ONBOOT` parameter of the capturing interfaces to *yes* in the interface configuration files. The network interfaces configuration can be found in `/etc/sysconfig/network-scripts/devices/ifcfg-ethX` (where *X* represents the necessary network interface). Alternatively, use the graphical utility **system-config-network** to set the appropriate interfaces to "activate device when computer starts".

4.9 Enabling Multibyte Fonts (Optional, but Recommended)

For PDF generation with multibyte character content, additional fonts need to be enabled. These fonts need to be made available to Java. Use the following command to copy (or move) the RUEI-installed fonts to the appropriate Java directory:

```
cp /var/www/ruei/include/bi_publisher/fonts/* \
/u01/app/oracle/product/11.1.0/db_1/jdk/jre/lib/fonts/
```

4.10 Mail (MTA) Configuration (Optional, Reporter Only)

RUEI assumes a working local MTA for sending PDF reports and E-mail alerts. By default, Enterprise Linux uses the Sendmail MTA. By default, Sendmail will deliver the E-mail directly to the destination MTA. If this behavior is not according to your needs or policies, sending mail via a SmartHost (relay) might be an alternative. To configure a SmartHost in Sendmail, do the following:

1. Find the line which contains the Smart Host setting in `/etc/mail/sendmail.mc`. Modify the `SMART_HOST` setting to your needs. For example:

```
define('SMART_HOST', 'my.example')dnl
```

2. Generate the new configuration into a new `sendmail.cf` by executing the following command:

```
make -C /etc/mail
```

3. Restart sendmail. For example:

```
/etc/init.d/sendmail restart
```

4.11 SNMP (Optional, Reporter Only)

You can download the RUEI MIB definition file through the Reporter interface. This definition file can be added to the SNMP manager. The procedure for downloading the MIB file is described in the *Oracle Real User Experience Insight User Guide*.

4.12 Configuring Automatic Browser Redirection (Optional)

To have the browser automatically redirected to the correct RUEI path, create the file `/var/www/html/index.html` with the following content:

```
<head>
<meta http-equiv="REFRESH" content="0;URL=/ruei/">
</head>
```

4.13 Configuring Reporter Communication (Split-Server Setup Only)

A password-less SSH connection must be setup between the Moniforce user from the Reporter system to each Collector system. Do the following:

1. Logon to the Reporter server as root. Issue the following commands:

```
su - moniforce
ssh-keygen -P ""
```

Press **Enter** to accept the defaults.

2. Logon as root on each of the Collector systems. Issue the following commands:

```
su - moniforce
cd ~/.ssh
ssh root@Reporter cat /var/opt/ruei/.ssh/id_rsa.pub >> authorized_keys
```

(you will need to specify the Reporter system root password)

```
chmod 600 authorized_keys
```

3. Check that it is now possible to execute a remote command (as `moniforce` user) on the Reporter system without using a password. For example:
 - Logon as root on the Reporter server.
 - Logon as moniforce user: `su - moniforce`.
 - Execute a remote `pwd` command: `ssh Collector pwd`.
 - Enter yes to the question "Are you sure you want to continue connecting (yes/no)?".
 - The command should return `/var/opt/ruei`.
4. The above steps must be performed for each Collector!

Note: If the connection between the Reporter and the Collector(s) has not been correctly configured, you will receive an authorization error when you try to register the remote Collector.

4.14 Verifying Successful Installation of RUEI

On completion of the Initial Setup Wizard (described in [Section 5.2, "Performing Initial RUEI Configuration"](#)), you can verify your installation by selecting **System**, the **Status**. All system indicators should report OK. Note Status notification will indicate "Unknown" because no system alerts have yet been configured. This is fully described in the *Oracle Real User Experience Insight User Guide*.

4.15 Upgrading From RUEI 4.5.x to 5.0

This section describes the procedure for upgrading an existing RUEI 4.5.x installation to release 5.0. For information on upgrading to RUEI 5.0 from a release prior to 4.5.x, please contact Customer Support.

The upgrade procedure needs to be performed on the Reporter system, as well as all required Collector systems. All actions must be performed by the `root` user. Be aware that when RUEI processing is stopped during the upgrade procedure, system notification alerts may be generated. These can be safely ignored.

Important: Before proceeding with the upgrade, make a backup of your configuration. This is necessary if you need to perform a rollback (described in [Section 4.15.2, "Rolling back an Upgrade"](#)). To do so, select **System**, then **Maintenance**, and then **Backup and Restore**. The procedure is fully described in the *Oracle Real User Experience Insight User Guide*. In addition, it is *strongly* recommended you carefully review the information in [Section 4.15.1, "Differences Between 4.5.x and 5.0"](#) before performing an upgrade.

Upgrading Accelerator Packages

If your RUEI installation makes use of accelerator packages (such as for Oracle E-Business Suite or Siebel), these *must* be upgraded at the same time as the RUEI system. Otherwise, your system may become unreliable. Ensure you following the sequence of steps described in the rest of this section.

Upgrading the RUEI System

The information in this section should be reviewed carefully before beginning the upgrade of the RUEI system and any required accelerator packages.

Note: Currently, any defined password security policies are not applied until user logon. For this reason, it is recommended you carefully review all defined users and password security policies. In addition, you should remove all disabled user accounts prior to upgrade.

When upgrading, ensure all steps are performed in the following sequence:

1. Login to the Reporter system as `root`. Within the `/root` directory, unzip the RUEI zip file, and go to the directory containing the application files. Use the following commands:

```
cd /root
unzip Vxxxx.zip
cd RUEI/50
chmod +x ruei-upgrade-4.5-5.0.sh
```

2. Stop all processing by issuing the following command:

```
./ruei-upgrade-4.5-5.0.sh stop_ruei
```

3. RUEI 5.0 will be installed in the directory `/opt/ruei`, while configuration and log files are stored in the directory `/var/opt/ruei`. Before upgrading to the new RPMs, a number of environment changes need to be made. These are performed by the upgrade script using the following command:

```
./ruei-upgrade-4.5-5.0.sh rpm_pre_install
```

4. Before upgrading, obsolete versions of the Oracle Instant Client and PHP RPMs need to be uninstalled. To do so, use the following commands:

```
rpm -e php-oci8
rpm -e oracle-instantclient-sqlplus
rpm -e oracle-instantclient-basic
rm -rf /usr/lib/oracle/11.1.0.1
```

5. Install the new versions of the Oracle Instant Client RPMs using the following commands:

```
cd /root/RUEI/IC/
rpm -Uhv oracle-instantclient11.1-*
cd /root/RUEI/PHP/
rpm -Uhv php-oci8-*
```

6. Install the PHP LDAP RPM using the following commands:

```
cd /mnt/dvd/Server
rpm -Uhv php-ldap-11gR1-*
```

Note: If you upgrade your PHP installation (for example, using Yum), this can overwrite changes you previously made to the `/etc/php.ini` file. Therefore, you should be prepared to re-install the Zend Optimizer.

7. Add the `/etc/ruei.conf` file to contain the following lines:

```
export JAVA_HOME=/u01/app/oracle/product/11.1.0/db_1/jdk/jre
export INSTANTCLIENT_DIR=/usr/lib/oracle/11.1/client64
#
# Do not change the information below.
#
export TNS_ADMIN=/var/opt/ruei
#
export PATH=${INSTANTCLIENT_DIR}/bin:${PATH}
export LD_LIBRARY_PATH=${LD_LIBRARY_PATH}:${INSTANTCLIENT_DIR}/lib
export LD_LIBRARY_PATH=${LD_LIBRARY_PATH}:${JAVA_HOME}/lib/amd64
export LD_LIBRARY_PATH=${LD_LIBRARY_PATH}:${JAVA_HOME}/lib/amd64/server
```

An example of this file is included in the RUEI distribution pack. Note if the Oracle database has been installed to a different location than that specified in the `JAVA_HOME` setting, you should specify the required location. Ensure the file is readable by the `moniforce` user by issuing the following command:

```
chmod 644 /etc/ruei.conf
```

8. A new PDF writer is introduced in this RUEI version, and it needs to be made available to the Apache daemon. Within the `/etc/sysconfig/httpd` file, remove the lines containing the `LD_LIBRARY_PATH` and `TNS_ADMIN` path settings, and replace with the following line:

```
source /etc/ruei.conf
```

9. Create the following PHP settings in the `/etc/php.d/ruei.ini` file:

```
session.gc_maxlifetime = 14400
memory_limit = 96M
upload_max_filesize = 128M
post_max_size = 128M
```

10. If you need to upgrade your accelerator packages, within the `/root` directory, unzip the RUEI 5.0 package, and all required accelerator zip files. Then go to the directory containing the application files, and install the associated RPMs. Use the following commands:

```
cd /root
unzip Vxxxx.zip
cd /root/RUEI/50
rpm -Uhv ux-*
```

11. On the Reporter system, and each required Collector system, convert all SSL keys to the new required format by using the following command:

```
./ruei-upgrade-4.5-5.0.sh convert_sslkeys
```

For each required SSL, the script will ask you to specify and confirm the 4.5.x activation password, and a key passphrase. If the SSL key has been installed without a passphrase, this should be left blank.

12. Repeat steps 1 - 10 for each Collector system.
13. Enable additional fonts for PDF generation. Because the PDF generator uses Java libraries, these need to be made available to Java. Copy (or move) the RUEI included fonts to the appropriate Java directory. For example:

```
cp /var/www/ruei/include/bi_publisher/fonts/* \
/u01/app/oracle/product/11.1.0/db_1/jdk/jre/lib/fonts/
```

14. Upgrade certain administrative information using the following command:

```
./ruei-upgrade-4.5-5.0.sh rpm_post_install
```

15. Login to the Reporter system as `root`, go to the required directory, and re-initialize the database using the following commands:

```
cd /root/RUEI/50
./ruei-upgrade-4.5-5.0.sh reinitialize
```

16. Because the storage of failed hits, pages, and services has changed in 5.0, they need to be converted using the following command:

```
./ruei-upgrade-4.5-5.0.sh convert_rolling_cubes
```

This may take several minutes. Any warnings generated by the script can be safely ignored.

17. Re-start RUEI using the following command:

```
./ruei-upgrade-4.5-5.0.sh start_ruei
```

18. Re-start the Apache Web server using the following command:

```
/etc/init.d/httpd restart
```

19. If you require multiple-byte character set support, issue the following command to install all optional fonts. Alternatively, install the multi-byte character sets necessary to meet your NLS requirements.

```
cd /mnt/dvd/Server
rpm -Uhv fonts-*
```

Troubleshooting Upgrade Problems

The upgrade script `ruei-upgrade-4.5-5.0.sh` logs its actions in the file `/tmp/ruei-upgrade-4.5-5.0.log`. If you encountered any problems during the upgrade, please attach this file to any request to Customer Support.

Note: Be aware that any 4.5.x backup you previously created cannot be used after your system has been upgraded to version 5.0. Therefore, it is recommended you create a 5.0 backup after completion of the upgrade procedure.

4.15.1 Differences Between 4.5.x and 5.0

This section highlights a number of reporting differences you may notice between versions 4.5.x and 5.0. Note an overview of all functional changes introduced in version 5.0 is available in the *Release Notes*, and the *Oracle Real User Experience Insight User Guide* contains a complete description of all available functionality.

Session Diagnostics

In version 4.5.x, URL strings were reported in their raw format. For example, `/doc/My%20Document.html`. In 5.0, URL-encoded bytes are removed, and URL strings are formatted. For example, the previous URL would now be reported as `/docs/My Document.html`. Note how the `%20` part is replaced by a space character. In addition, any NLS character encoding (such as Chinese) is now used to report the URL, rather than its URL-encoded form. There is one exception to this: the special

characters /, ?, ;, %, =, and #, when present in the encoded form, are not decoded, but left "as is".

In order to minimize disruption, the upgrade procedure creates a new filter, based on the existing 4.5.x filter, for each defined filter. Hence, after upgrading, you will notice there are two filters: the 4.5.x filter will be applicable to the legacy 4.5.x data, and 5.0 filters will be used for monitoring 5.0 data. It is recommended you review all KPIs, SLAs, and reports that include URL-based definitions (such as filters or requirements). You are free to delete the 4.5.x filters whenever you decide 4.5.x data no longer needs to be reviewed.

URL Arguments

The handling of URL arguments within applications and custom dimensions definitions, as well as user ID matching, has also changed in 5.0.

Each URL argument has a *name=value* combination. In 4.5.x, the *name* part was decoded by RUEI. Therefore, all URL argument names had to be specified in their formatted version. For example, foo\$bar\$baz. In 5.0, URL argument names are no longer decoded, but reported in their raw (original) form. Therefore, they must also now be specified in their raw form. For example, foo%24bar%24baz.

Note the upgrade procedure automatically converts all URL argument name definitions to the new format. Therefore, it is not necessary to manually update them. However, be aware the reporting of these URL argument names will appear different in 5.0.

Conversion of Monitored Strings

The functionality that allows you to monitor strings that appear on pages (such as functional errors and page content checks) has changed in 5.0. All defined strings are automatically converted to their Unicode (UTF-8) equivalent.

Enriched Data Exchange Facility

The Enriched data exchange facility enables the alternative analysis of the data collected by RUEI. In particular, it allows you to combine the data collected by RUEI with other warehouse data. For example, a Customer Relationship Management (CRM) or Business Intelligence (BI) system. The exported data is based on pageviews, and is in XML format.

The XSD file that defines the structure of the exported XML files has changed in 5.0. Therefore, If you have systems that use data derived from the 4.5.x Enriched data facility, you will need review the new XML structure, and modify the operation of these systems as necessary. The Enriched data exchange facility is fully described in the *Oracle Real User Experience Insight User Guide*.

4.15.2 Rolling back an Upgrade

This section describes the procedure to rollback to version 4.5.x after 5.0 upgrading to version 5.0.

Important: Be aware that it may not be possible to restore your system to its exact state prior to upgrading. In addition, it is recommended you contact Customer Support before rolling back an upgrade.

1. Login to the Reporter system as `root`. Within the `/root` directory, unzip the RUEI zip file, and go to the directory containing the application files. Use the following commands:

```
cd /root
unzip Vxxxx.zip
cd RUEI/50
chmod +x ./ruei-rollback-5.0-4.5.sh
```

2. Run the `ruei-rollback-5.0-4.5.sh` script as `root`. This script performs all necessary rollback actions not covered by the RPM replacement.
3. Stop all RUEI processing by issuing the following command:

```
./ruei-rollback-5.0-to-4.5.sh stop_ruei
```

4. In RUEI 5.0, the product is installed in the directory `/opt/ruei`, while configuration and log files are stored in the directory `/var/opt/ruei`. Before downgrading to the old RPMs, a number of environment changes need to be made. These are performed by the downgrade script using the following command:

```
./ruei-rollback-5.0-4.5.sh rpm_pre_install
```

5. Edit the `/etc/sysconfig/httpd` file, and deleting the line referring to `/etc/ruei.conf`, and adding the following lines:

```
export LD_LIBRARY_PATH=/usr/local/instantclient/lib
export TNS_ADMIN=/home/moniforce
```

6. Downgrade the RUEI software using the following commands:

```
cd /root/RUEI/45
rpm -Uhv --oldpackage ux-*
```

7. Remove the new versions of the Oracle Instant Client and PHP RPMs using the following commands:

```
rpm -e oracle-instantclient11.1-sqlplus
rpm -e oracle-instantclient11.1-basic
rpm -e php-oci8-11gR1
```

8. Restore the previous versions of the Oracle Instant Client and PHP RPMs using the following commands:

```
cd /root/RUEI/IC
rpm -Uhv oracle-instantclient-basic-11.1.0.*.rpm
rpm -Uhv oracle-instantclient-sqlplus-11.1.0.*.rpm
cd /root/RUEI/PHP/
rpm -Uhv php-oci8-5.1.6-*
```

9. Restore symlinks to the Oracle Instant Client using the following commands:

```
mkdir -p /usr/local/instantclient
ln -fsv /usr/lib/oracle/11.1.0.1/client64/lib /usr/local/instantclient
ln -fsv /usr/lib/oracle/11.1.0.1/client64/bin /usr/local/instantclient
```

10. Repeat steps 1 - 8 for each Collector system.

11. Restore the backup of your 4.5.x configuration. You will need to copy the backup file to the Reporter system, and store it in a location the `moniforce` user can access, such as `/tmp`. Then run the following commands:

```
cd /root/RUEI/50
./ruei-rollback-5.0-4.5.sh restore_backup /tmp/backup.tar.gz
```

replacing `/tmp/backup.tar.gz` with the name and location of the required backup file.

12. Undo a number of conversion actions by issuing the following command:

```
./ruei-rollback-5.0-4.5.sh rpm_post_install
```

13. Re-start RUEI using the following command:

```
./ruei-rollback-5.0-4.5.sh start_ruei
```

14. Because SSL keys are migrated to a different storage method during the upgrade, but no downgrade procedure is available, you will need to re-implement your SSL keys. This is fully described in the *Oracle Real User Experience Insight User Guide*.

15. Optionally, convert the storage of failed hits, pages, and services back to 4.5.x format using the following command:

```
./ruei-rollback-5.0-4.5.sh convert_rolling_cubes
```

Troubleshooting Rollback Problems

The rollback script `ruei-rollback-5.0-4.5.sh` logs its actions in the file `/tmp/ruei-rollback-5.0-4.5.log`. If you encountered any problems during the rollback, please attach this file to any request to Customer Support.

Configuring RUEI

This chapter describes the procedure for initially configuring RUEI. This task is performed by the individual within your organization who has been assigned the role of RUEI **Administrator**. For more information about roles, see the *Oracle Real User Experience User Guide*.

5.1 Introduction

In order to get RUEI up and running, you will need to have prepared the server systems for RUEI, and installed the RUEI software. This is described in [Chapter 2, "Installing RUEI"](#). After that, you are required to specify the installation type and mail setup (described in [Section 5.2, "Performing Initial RUEI Configuration"](#)), and then perform some post-installation configuration (described in [Section 5.4, "Performing Post-Installation Configuration"](#)). This is necessary in order to start reporting. It includes deciding how pages and users will be identified, and specifying the scope of monitoring in your network environment. Finally, you will need to define the system's initial users, as described in [Section 5.4.6, "Authorizing Initial Users"](#). Note that if you are installing a split-server configuration, you will need to configure each Collector system. This is described in [Section 5.3, "Configuring a Collector System"](#).

Caution: The configuration of RUEI should be discussed with someone with a detailed knowledge of your organization's network topology.

5.2 Performing Initial RUEI Configuration

In order for RUEI to start data monitoring and reporting, it must be configured with some information about your network infrastructure. Once completed, user traffic reporting is available. Note that this initial configuration can be changed later, as necessary. It is only intended to provide RUEI with sufficient information to start real-user monitoring and reporting.

To perform the initial RUEI configuration, do the following:

1. Start the Initial setup wizard by pointing your browser at `https://Reporter/ruei`. The dialog shown in [Figure 5-1](#) appears:


Figure 5–1 Logon Dialog Box




Specify the admin user, and the RUEI Administration password defined with the set-admin-password script (defined in Section 2.6.4, "Installation of the RUEI Software"). When ready, click **Login**. The dialog shown in Figure 5–2 appears.

Note: The first time a user logs on, they receive a warning that the Web server was unable to verify the identify of the site’s certificate. Depending on your security policies, you can either choose to accept this certificate permanently, temporarily for this session, or reject the certificate. Alternatively, you can purchase a certificate from a Certificate Authority (CA). You can also create an SSL certificate. For more information, visit http://httpd.apache.org/docs/2.2/ssl/ssl_faq.html#realcert.

Figure 5–2 Initial Setup Wizard Dialog




2. Click **Next** to proceed with configuration. The dialog shown in Figure 5–3 appears:

Figure 5–3 Installation Type Dialog

- Use the radio buttons to select the required installation type. A Reporter system performs both data collection and reporting, and is the default configuration. A Collector configuration only performs data monitoring. After making your selection, click **Next**. The dialog shown in [Figure 5–4](#) appears.

Important: Configuration of a RUEI system as a Collector (that is, as part of a split-server configuration) is only possible during this initial configuration phase; and this selection cannot be changed later. You should fully understand the implications of your selection before proceeding. Also, see [Section 5.3, "Configuring a Collector System"](#) for important information about registering the Collector with a Reporter system.

Figure 5–4 Mail Setup Dialog


- Specify the requested information. The e-mail information is used to configure RUEI's interface to your internal network, and will be used for reporting problems. When you have entered the required information, click **Next**. The dialog shown in [Figure 5-5](#) appears.

Figure 5-5 Settings Overview Dialog



- Check that the information specified in the settings overview is correct. You can use **Back** and **Next** to move between dialogs as necessary. When ready, click **Next**. The dialog shown in [Figure 5-6](#) appears.

Figure 5-6 Applying Settings Dialog




- This dialog indicates how far the system has got in applying your specified settings. Typically, this process takes a maximum of 15 minutes. When finished, click **Finish** to close the dialog.

5.3 Configuring a Collector System

If you selected a Collector configuration (Figure 5-3), the dialog shown in Figure 5-7 appears after logon:


Figure 5-7 Collector Information Panel



To register a Collector to a Reporter system, do the following:

1. Within the Reporter system, select **System**, then **Maintenance**, and then **Network data collectors**. The Network data collectors window appears.
2. Select **Configuration**, and then **Register remote Collector**. The Register Collector dialog shown in Figure 5-8 appears.

Figure 5-8 Register Collector Dialog



3. Enter the IP address of the Collector. Optionally, you can also specify a brief description of the attached Collector. When ready, click **Register**. On return to the Network data collectors window, the new Collector should be listed.

5.3.1 Resetting a Collector System

As mentioned earlier, it is not possible to select a Collector type installation for a system, and later change it to a Reporter installation. The only way you can change its installation type is by repeating the installation procedure on the required system, and selecting Reporter as the installation type (shown in Figure 5-3) when re-running the initial setup wizard.

5.4 Performing Post-Installation Configuration

In order to start reporting, the RUEI needs certain information about the monitored network environment. It is important to understand that RUEI is designed to work within a wide range of network environments. Therefore, the configuration choices you make will affect the accuracy and usability of the reported data. It is strongly recommended that you carefully review the settings described in this section.

5.4.1 Specifying the Cookie Technology

Within RUEI, session information is based on cookies. Therefore, RUEI needs to know and understand the cookie technology (or technologies) your organization is using. The procedure to configure this is described in the *Oracle Real User Experience Insight User Guide*. The structure of supported cookie technologies is also explained in the *Oracle Real User Experience Insight User Guide*.

If cookie information is not available, user tracking is based on visitor IP address. This can lead to unreliable session information. For example, in the case of users behind a proxy server, all users coming from that network would be identified as the same user.

5.4.2 Adding/Uploading HTTP SSL Keys

Uploading SSL keys to the system is extremely important if most of your HTTP traffic is based on SSL sessions. Without the SSL keys being available to the system, the Collector will not be able to decrypt the SSL session traffic. In these circumstances, further configuration of cookies, user identification, and application pages would make little sense. Ensure that you upload and activate your HTTPS SSL keys as early on as possible in the configuration process. The management of SSL keys is fully described in the *Oracle Real User Experience Insight User Guide*.

5.4.3 Specifying How Users are Identified

Within RUEI, user identification is first based on the HTTP Authorization field. After that, it is derived from the supplied GET/POST argument within URLs. Therefore, if you are using arguments within URLs, the item within these used for user identification must be specified in order to provide reliable results. This is fully described in the *Oracle Real User Experience Insight User Guide*.

5.4.4 Naming Pages

Page identification within RUEI is based on applications. Essentially, an application is a collection of Web pages. This is because pages on a Web site are typically bound to a particular application. For each page that the system detects, it uses the available application definitions to assign a name to it. Note that information about any pages that could not be identified using these definitions is discarded, and, therefore, not available through reports and the data browser. This is fully described in the *Oracle Real User Experience User Guide*.

5.4.5 Specifying the Scope of Monitoring

Within RUEI, you control the scope of traffic monitoring by specifying which TCP ports the SYSTEM should monitor. Obviously, no information is available for non-monitored ports. In addition, you can restrict monitoring to specific servers and subnets. This is fully described in the *Oracle Real User Experience Insight User Guide*.

5.4.6 Authorizing Initial Users

In order for users to start working with RUEI, you will need to authorize the required users. Only one user, the Administrator, is available after installation. The procedure to set the initial admin user password is described in [Section 2.6.4, "Installation of the RUEI Software"](#). All other required users must be created and assigned the necessary roles and access permissions through the Reporter GUI. In particular, it is recommended that you create a dedicated Security Officer account to finalize the security-related configuration. User roles, creation and management are fully described in the *Oracle Real User Experience Insight User Guide*.

Note that passwords are case sensitive, while user names are not. It is recommended that you do not include any diacritic characters, such as umlauts.


5.5 Verifying and Evaluating Your Configuration

To ensure the quality and quantity of data being collected and analyzed by your RUEI system, it is strongly advised that you verify the system's configuration using some core metrics. These are described in the following sections.

5.5.1 Viewing a Traffic Summary

You can open an overview of the monitored network traffic by selecting **System**, then **Status**, and then **Data processing**. This provides you with immediate information about hits, pages, and session processing, as well as the system load. An example is shown in [Figure 5–9](#):

Figure 5–9 Data Processing Dialog



The precise number of percentage of identified sessions, pageviews, and hits relies heavily on your exact configuration. If you intend to measure all traffic, it is recommended that at least 80% of sessions, pageviews, and hits are reported as

"identified". It is also recommended that you regularly review the reported numbers and percentages to ensure the quality and quantity of reported data.

Important: After initial configuration of cookies, user identification, and application page structure, the system will take at least 5 - 10 minutes before the **Sessions/Hits/Pageviews** tabs are updated with green bars. If, after 20 - 30 minutes after initial configuration, there is no green bars showing on any of the tabs, please review your initial RUEI configuration. If the bars do not indicate any activity at all, please review your system's network card configuration as outlined in [Section 1.7, "Network Requirements"](#).

5.5.2 Confirming Data Collection

At this point, RUEI should be collecting data from each of its associated Collectors. You can easily check the status of these Collectors by selecting **System**, then **Status**, and then **Collector status**. This opens the Network data collectors window. This is fully described in the *Oracle Real User Experience Insight User Guide*.

It is important to understand that the data being collected by Collector system(s) is offered to the RUEI data processing module for further analysis. If no data is collected, there is no means by which it can be processed.

Troubleshooting

This appendix highlights the most common problems encountered when installing RUEI, and offers solutions to locate and correct them. The information in this appendix should be reviewed before contacting Customer Support.

Support Web sites

Information on a wide variety of topics is available via the Oracle Web site (http://www.oracle.com/enterprise_manager/user-experience-management.html). It is recommended that you visit it regularly for support announcements.

In addition, detailed technical information is available via the Support Web site (<https://metalink.oracle.com>). This includes information about service pack availability, FAQs, training material, tips and tricks, and the latest version of the product documentation. A valid user name and password is required to access this Web site.

Contacting Customer Support

If you experience problems with the installation or configuration of the RUEI, you can contact Customer Support. However, before doing so, it is strongly recommended that you create a Helpdesk report file of your installation. To do so, select **System**, then **Configuration**, and then **Helpdesk report**. This file contains extended system information that is extremely useful to Customer Support when handling any issues that you report.

A.1 The `prepare_uxinsight_db.sh` Script Fails

If the `prepare_uxinsight_db.sh` script fails, this can be because the database listener has not been started correctly due to a failing DNS look up. To resolve this problem, do the following:

- Ensure the `/etc/hosts` file includes your host.
- Ensure entries in the `/etc/nsswitch.conf` file are specified in the required (sequence hosts: files DNS).

A.2 The Applying Settings Dialog Hangs

If the Applying settings dialog (Figure 5-6) hangs after performing the initial configuration (described in Section 5.2, "Performing Initial RUEI Configuration"), it is recommended that you do the following:

- Review the specified network settings and ensure that they are correct.

- Ensure that the time zone is explicitly set in your PHP installation. For more information, see [Section 2.5.1, "PHP Configuration"](#).

A.3 Starting Problems

If the system does not seem to start, or does not listen to the correct ports, do the following:

- Restart each Collector service. To do so, select **System**, then **Maintenance**, then **Network data collectors**, select each attached Collector, and select the **Restart** option from the menu. This is described in more detail in the *Oracle Real User Experience Insight User Guide*.
- Review your network filter definitions. This is described in the *Oracle Real User Experience Insight User Guide*. In particular, ensure that no usual network filters have been applied. This is particularly important in the case of VLANs.
- Ensure that RUEI is listening to the correct protocols and ports. This is described in the *Oracle Real User Experience Insight User Guide*.
- Verify that the Collector interfaces are *up*. This is described in the [Section 2.2, "Installing the Linux Operating System"](#).

Resources and Log Files

If during, or directly after running the Initial setup wizard (described in [Section 5.2, "Performing Initial RUEI Configuration"](#)), the system returns an error, there are the following resources and log files available to help you in debugging:

- `/var/opt/ruei/processor/log/gui_debug.log`: a proprietary debug and log file that shows low-level system information. Although its contents may be difficult to read, you can find standard system error messages listed here.
- `/var/log/httpd/access_log` and `/error_log`: the Apache daemon access and error log files. If any part of the HTTP or PHP execution of the RUEI user interface is in error, it will show up in these log files. (Note that these are *not* the log files used by RUEI for HTTP data analysis).

Root-Cause Analysis

Before starting to address specific issues, it is important to understand the basic operation of data collection, data processing, and data reporting. Any root-cause analysis of RUEI problems should take the following:

- Verify data collection. Select **System**, then **Status**, and then **Collector status**. Select a Collector from the displayed list, and verify that the system interfaces are showing traffic activity on TCP, Ethernet, and HTTP level.
- In addition, verify that there are no problems with the SSL data decryption. It is normal that some errors occur (especially shortly after startup). But if SSL traffic is to be decrypted, the error rate can never be 100%.
- Verify data processing. Select **System**, then **Status**, then **Data processing**. A screen similar to the one shown in [Figure 5-9](#) appears. It should indicate some activity.

A.4 Data Collection Problems

If the data collection service is not running, or will not start, do the following:

- Ensure the network cards used for data collection are running in promiscuous mode. This can be verified by issuing the command `ifconfig ethN` (where *N* is

the number of the network interface being used for data collection). It should return an output similar to the following:

```
ethn      Link encap:Ethernet  HWaddr 00:15:17:3E:26:AF
          UP BROADCAST RUNNING PROMISC MULTICAST  MTU:1500  Metric:1
          RX packets:0 errors:0 dropped:0 overruns:0 frame:0
          TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:1000
          RX bytes:0 (0.0 GiB)  TX bytes:0 (0.0 GiB)
          Memory:b9120000-b9140000
```

- If the network interface is not available, make sure the ONBOOT parameter is set to YES, as described in [Section 2.2.4, "Network Configuration"](#).
- If the network interface is not yet in promiscuous mode, set it by issuing the following command: `ifconfig ethN promisc` (where *N* is the number of the network interface being used for data collection).
- Verify there is *no* IP address assigned to the network interface being used for data collection. If there is a configured IP address, remove it.

Note: Do not set to 0.0.0.0 or 127.0.0.1. Remove the configured IP address completely.

A.5 Data Processing Problems

If, for any reason, data processing does not start, try to restart it by selecting **System**, then **Maintenance**, and then **System Reset**. The System reset wizard appears. Select the **Restart system processing** option. Note that restarting system processing can take between 5 and 30 minutes.

In general, if no data is being processed, verify your system's configuration as described in [Section 5.5, "Verifying and Evaluating Your Configuration"](#). If you do not apply any configuration to the system, no data processing will take place.

If you are using an environment with multiple Collectors, ensure all Collectors are up and running normally. To do so, select **System**, then **Status**, and then **Collector status**. An failing Collector can become a block to further data processing of the system's data.

A.6 E-Mail Problems

Sending E-mails is RUEI functionality that is handled on a system level, together with your Mail Transfer Agent (MTA), such as Sendmail or Postfix. If problems occur when sending E-mails, do the following:

- If mail is sent correctly by RUEI to your MTA, the user interface will report "Message sent successfully" when you attempt to send a daily, weekly, or monthly report manually.
- If mail could not be sent correctly by RUEI to your MTA, verify that the MTA is up and running. Alternatively, analyze the mail settings by selecting **System**, then **Maintenance**, and **Mail configuration**.
- If the mail was sent successfully, but not delivered to the recipient, analyze the operation of your MTA to further identify the root cause of the mails that are not delivered.

Common issues with E-mail delivery often involve an incorrectly configured MTA, or an MTA that is not allowed to send E-mail within the Data Center or corporate network.

A.7 SSL Decryption Problems

In order to decrypt SSL traffic, the Collector needs to have the SSL key and certificate available. To enable SSL decryption, you should do the following:

- Upload the SSL key through the appropriate Collector.
- Enable the SSL key by entering the required decryption passphrase (when applicable).

The certificate needs to be uploaded to the Collector(s) by selecting **Configuration**, then **Security**, and then **SSL keys**. To check the status of the SSL decryption, select **System**, then **Status**, and then **Collector status**, and select the Collector for which you want SSL decryption analysis. Within the **SSL encryption** page, note the following:

- Decryption errors will occur if there is no SSL key uploaded.
- The percentage of successful decryption will be a low number shortly after uploading and activating the appropriate SSL keys.
- This percentage should rise in the first minutes and hours after uploading the SSL keys.

RUEI accepts PKCS#12 and PEM/DER encoding of SSL keys and certificates. Basically, this means both the certificate and key should be concatenated into one file. If you have separate key and certificate files, you can create a PKCS#12-compliant file by issuing the following command:

```
openssl pkcs12 -export -in certificate.cer -inkey key.key -out pkcs12file.p12
-passout pass:yourpassphrase
```

Where:

- *certificate.cer* is your CA root certificate file.
- *key.key* is the server's SSL key file.
- *pkcs12file.p12* is the output file name for the PKCS#12-encoded file.
- *yourpassphrase* is the passphrase you want to use to protect the file from unwanted decryption.

For example, consider the situation where the CA root certificate filename is *ca_mydomainroot.cer*, the server's SSL key is *appsrv12.key*, you want the output file to be called *uxssl.p12*, and want to protect this file with the passphrase *thisismysecretphrase*. The following command is required:

```
openssl pkcs12 -export -in ca_mydomainroot.cer -inkey appsrv12.key -out uxssl.p12
-passout pass:thisismysecretphrase
```

A.8 Missing Packages and Fonts Error Messages

It is *strongly* recommended that you follow the installation procedure and settings described in [Section 2.2.5, "Package Installation"](#). In particular, you should not perform a "minimal" installation of Oracle Enterprise Linux. If you do so, it can lead to a wide range of reported problems, depending on the components not included in the installation, but required by RUEI.

The most common of these are reported `fontconfig` error messages in the `/var/log/http/error_log` file. These can be fixed by installing the following fonts:

- `urw-fonts-noarch v2.3`
- `ghostscript-fonts-noarch v5`
- `dejavu-lgc-fonts-noarch v2`
- `liberation-fonts v0.2`
- `bitmap-fonts v0.3`
- `bistream-vera-fonts-noarch v1.10`

Depending on your language settings, install all other required fonts.

However, other possible error messages include reported missing packages (such as `librsvg2`).

When a Yum repository is available, all dependencies available on the Enterprise Linux 5.x DVD can be installed by issuing following command:

```
yum -y install gcc gcc-c++ compat-libstdc++-33 glibc-devel libstdc++-devel \
elfutils-libelf-devel glibc-devel libaio-devel sysstat perl-URI net-snmp \
sendmail-cf httpd php php-gd php-pear php-mbstring phpldap bitstream-vera-fonts \
librsvg2 xorg-x11-xinit
```

However, be aware that additional RPMs shipped with the RUEI installation zip file still need to be installed according to the procedure described in [Section 2.6, "Installing the RUEI Software"](#).

A.9 ORA-xxxxx Errors

If you receive any Oracle database errors, do the following:

- Ensure that the `/etc/sysconfig/httpd` file contains the following lines:

```
export LD_LIBRARY_PATH=/usr/local/instantclient/lib
export TNS_ADMIN=/home/moniforce
```

If you have to add these lines, restart the Apache Web server using the following command:

```
service httpd restart
```

- Ensure the same host name is specified in the `/var/opt/ruei/tnsnames.ora`, `/etc/sysconfig/network`, and `/etc/hosts` files.

Note if you make changes to any of these files, you may need to reboot the server.

A.10 Oracle DataBase Not Running

Verify the Oracle database is up and running by changing to the `moniforce` user and obtaining an SQL*Plus prompt with the following commands:

```
su - moniforce
sqlplus /@uxinsight
```

You should receive the SQL*Plus command line without being prompted for a password. This indicates that the Oracle wallet authentication was successful.

A.11 General (Non-Specific) Problems

If you are experiencing problems with the reporting module, or find its interface unstable, it is recommended that you do the following:

- Clear all content caching within your browser, and re-start your browser.
- Examine the error log. This is described in the *Oracle Real User Experience Insight User Guide*.
- Select **System**, then **Maintenance**, and then **Environment check** to verify the core components of the RUEI installation. This is described in more detail in the *Oracle Real User Experience Insight User Guide*.
- Select **System**, then **Status**, and verify correct operation of the core components by then selecting **Data Collection**, **Logfile processing**, and **Data processing**. If any of these components are in error, try to resolve them using the advice provided in this appendix.

A.12 Network Interface Not Up

If the network interface you intend to use for data collection is not *Up* (that is, the `ONBOOT=YES` parameter was not set), you can bring it immediately using the following command:

```
ifconfig ethN up
```

where *N* represents the necessary network interface.

Installation Checklist

This appendix provides a checklist of actions that should be complete, and information gathered, before starting to install the RUEI software. These include server and infrastructure readiness and configuration, as well as HTTPS encrypted traffic and alerting issues.

Server readiness

Base hardware and operating system requirements.

Intel/AMD 64-bit platform (minimum 2 dual-core CPUs).

Network connectivity:

- 10/100 MB NIC for office network connectivity.
- 10/100/1000 MB NIC for data collection connectivity.

Disk space: at least 400 GB (on high-performance RAID-5, RAID-10, or similar).

Memory: at least 16 GB RAM for single server.

OS: Oracle Enterprise Linux 64-bit or RedHat Enterprise Linux 64-bit 5.x.

The `ruei-check.sh` script reports no errors.

The EBS and PeopleSoft configuration zip files are available (only applicable if the EBS and/or PeopleSoft accelerators are to be installed).

Infrastructure readiness

Ensure easy placement and accessibility of the system.

Prepare rackspace in the Data Center cabinet with power sockets.

The server is accessible through remote ports:

- Port 80/443 for HTTP(S) traffic to the RUEI Web server.
- Port 22 for remote management over SSH/SCP.
- Port 25 (SMTP).
- Port 123 (NTP).
- Port 161/162 (SNMP).

Access to the Data Center on the appropriate day and time is arranged.

Network preparation for TAP/copy port is done and cables available in cabinet.

Server configuration completed (see below).

Main topology with proxies, load balancers, routers, switches, and so on, is known.

Infrastructure readiness	
<p>Main traffic flows throughout the infrastructure are known.</p> <p>VLAN topology, VLAD IDs, and IP addresses are known.</p> <p>The monitoring position for the RUEI server is located as close as possible to the firewall.</p> <p>The domains, applications, server farm(s), and/or VLANs to be monitored are identified.</p>	

Server configuration	
Complete the details below to for reference during server configuration.	
<p>Host name and domain name (optional).</p> <p>Data Center name.</p> <p>Placement date and time.</p> <p>Server IP, netmask, and default gateway.</p> <p>Server type (Collector/Reporter).</p> <p>NTP server IP and backup.</p> <p>DNS server IP and backup.</p> <p>Mail server and sender mail.</p> <p>Socket 0: collection port to TAP/switch name.</p> <p>Socket 1: collection port to TAP/switch name.</p> <p>Socket 2: rescue/maintenance interface.</p> <p>Socket 3: Office network to switch name.</p> <p>Socket 4: collection port to TAP/switch name.</p> <p>Socket 5: collection port to TAP/switch name.</p>	<reserved>

Data collection configuration	
Once in place, the server will start collecting data. Specify how much data is expected, and the technologies used.	
<p>HTTP traffic (in MB, pageviews, or hits per hour).</p> <p>Base technology for Web applications.</p> <p>Limits on amount of traffic to be captured:</p> <ul style="list-style-type: none"> ■ HTTP and HTTPS ports (if other than 80/443 HTTP/HTTPS). ■ VLAN traffic and VLAN IDs (optional). <p>Cookie technology.</p> <p>Page-labelling technology.</p> <p>Blind POST field names (such as passwd).</p> <p>User identification in URL (if other than login).</p> <p>Web service domains or networks.</p> <p>XML/SOAP envelopes (max 10).</p> <p>Chronos/EUM URL (for EBS and Forms).</p>	

HTTPS enablement

Specify the contact(s) for the required SSL keys to monitor encrypted traffic.

Name:	Name:
Function:	Function:
E-mail:	E-mail:
Phone/Mobile:	Phone/Mobile:
Keys (if not all):	Keys (if not all):

System health notifications

The system can trigger and send alerts for various components. Specify the users, notification methods, and details for each component.

Name:	Name:
Function:	Function:
E-mail:	E-mail:
Mobile:	Mobile:
SMS:	SMS:

Alerting via SNMP (optional)¹

SNMP management server.

SNMP community name.

SNMP version.

¹ RUEI provides a standard MIB to be imported into the SNMP manager.

Third-Party Licenses

This appendix contains licensing information about certain third-party products included with RUEI 4.5. Unless otherwise specifically noted, all licenses herein are provided for notice purposes only.

The sections in this appendix describe the following third-party licenses:

- [Apache Software License, Version 2.0](#)
- [OpenSSL](#)
- [PHP](#)
- [SpyC](#)
- [Prototype.js](#)
- [W3C](#)
- [JSON](#)
- [PNET](#)
- [Bitstream Vera Font](#)
- [Script.aculo.us](#)
- [PNGQuant.c](#)
- [Rwpng.c/Rwpng.h](#)

Apache Software License, Version 2.0

Apache License

Version 2.0, January 2004

<http://www.apache.org/licenses/>

TERMS AND CONDITIONS FOR USE, REPRODUCTION, AND DISTRIBUTION

1. **Definitions.** "License" shall mean the terms and conditions for use, reproduction, and distribution as defined by Sections 1 through 9 of this document.

"Licensor" shall mean the copyright owner or entity authorized by the copyright owner that is granting the License.

"Legal Entity" shall mean the union of the acting entity and all other entities that control, are controlled by, or are under common control with that entity. For the purposes of this definition, "control" means (i) the power, direct or indirect, to cause the direction or management of such entity, whether by contract or otherwise, or (ii) ownership of fifty percent (50%) or more of the outstanding shares, or (iii) beneficial ownership of such entity.

"You" (or "Your") shall mean an individual or Legal Entity exercising permissions granted by this License.

"Source" form shall mean the preferred form for making modifications, including but not limited to software source code, documentation source, and configuration files.

"Object" form shall mean any form resulting from mechanical transformation or translation of a Source form, including but not limited to compiled object code, generated documentation, and conversions to other media types.

"Work" shall mean the work of authorship, whether in Source or Object form, made available under the License, as indicated by a copyright notice that is included in or attached to the work (an example is provided in the Appendix below).

"Derivative Works" shall mean any work, whether in Source or Object form, that is based on (or derived from) the Work and for which the editorial revisions, annotations, elaborations, or other modifications represent, as a whole, an original work of authorship. For the purposes of this License, Derivative Works shall not include works that remain separable from, or merely link (or bind by name) to the interfaces of, the Work and Derivative Works thereof.

"Contribution" shall mean any work of authorship, including the original version of the Work and any modifications or additions to that Work or Derivative Works thereof, that is intentionally submitted to Licensor for inclusion in the Work by the copyright owner or by an individual or Legal Entity authorized to submit on behalf of the copyright owner. For the purposes of this definition, "submitted" means any form of electronic, verbal, or written communication sent to the Licensor or its representatives, including but not limited to communication on electronic mailing lists, source code control systems, and issue tracking systems that are managed by, or on behalf of, the Licensor for the purpose of discussing and improving the Work, but excluding communication that is conspicuously marked or otherwise designated in writing by the copyright owner as "Not a Contribution."

"Contributor" shall mean Licensor and any individual or Legal Entity on behalf of whom a Contribution has been received by Licensor and subsequently incorporated within the Work.

2. Grant of Copyright License. Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable copyright license to reproduce, prepare Derivative Works of, publicly display, publicly perform, sublicense, and distribute the Work and such Derivative Works in Source or Object form.

3. Grant of Patent License. Subject to the terms and conditions of this License, each Contributor hereby grants to You a perpetual, worldwide, non-exclusive, no-charge, royalty-free, irrevocable (except as stated in this section) patent license to make, have made, use, offer to sell, sell, import, and otherwise transfer the Work, where such license applies only to those patent claims licensable by such Contributor that are necessarily infringed by their Contribution(s) alone or by combination of their Contribution(s) with the Work to which such Contribution(s) was submitted. If You institute patent litigation against any entity (including a cross-claim or counterclaim in a lawsuit) alleging that the Work or a Contribution incorporated within the Work constitutes direct or contributory patent infringement, then any patent licenses granted to You under this License for that Work shall terminate as of the date such litigation is filed.

4. Redistribution. You may reproduce and distribute copies of the Work or Derivative Works thereof in any medium, with or without modifications, and in Source or Object form, provided that You meet the following conditions:

-
- You must give any other recipients of the Work or Derivative Works a copy of this License; and
 - You must cause any modified files to carry prominent notices stating that You changed the files; and
 - You must retain, in the Source form of any Derivative Works that You distribute, all copyright, patent, trademark, and attribution notices from the Source form of the Work, excluding those notices that do not pertain to any part of the Derivative Works; and
 - If the Work includes a "NOTICE" text file as part of its distribution, then any Derivative Works that You distribute must include a readable copy of the attribution notices contained within such NOTICE file, excluding those notices that do not pertain to any part of the Derivative Works, in at least one of the following places: within a NOTICE text file distributed as part of the Derivative Works; within the Source form or documentation, if provided along with the Derivative Works; or, within a display generated by the Derivative Works, if and wherever such third-party notices normally appear. The contents of the NOTICE file are for informational purposes only and do not modify the License. You may add Your own attribution notices within Derivative Works that You distribute, alongside or as an addendum to the NOTICE text from the Work, provided that such additional attribution notices cannot be construed as modifying the License. You may add Your own copyright statement to Your modifications and may provide additional or different license terms and conditions for use, reproduction, or distribution of Your modifications, or for any such Derivative Works as a whole, provided Your use, reproduction, and distribution of the Work otherwise complies with the conditions stated in this License.

5. Submission of Contributions. Unless You explicitly state otherwise, any Contribution intentionally submitted for inclusion in the Work by You to the Licensor shall be under the terms and conditions of this License, without any additional terms or conditions. Notwithstanding the above, nothing herein shall supersede or modify the terms of any separate license agreement you may have executed with Licensor regarding such Contributions.

6. Trademarks. This License does not grant permission to use the trade names, trademarks, service marks, or product names of the Licensor, except as required for reasonable and customary use in describing the origin of the Work and reproducing the content of the NOTICE file.

7. Disclaimer of Warranty. Unless required by applicable law or agreed to in writing, Licensor provides the Work (and each Contributor provides its Contributions) on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied, including, without limitation, any warranties or conditions of TITLE, NON-INFRINGEMENT, MERCHANTABILITY, or FITNESS FOR A PARTICULAR PURPOSE. You are solely responsible for determining the appropriateness of using or redistributing the Work and assume any risks associated with Your exercise of permissions under this License.

8. Limitation of Liability. In no event and under no legal theory, whether in tort (including negligence), contract, or otherwise, unless required by applicable law (such as deliberate and grossly negligent acts) or agreed to in writing, shall any Contributor be liable to You for damages, including any direct, indirect, special, incidental, or consequential damages of any character arising as a result of this License or out of the use or inability to use the Work (including but not limited to damages for loss of goodwill, work stoppage, computer failure or malfunction, or any and all other commercial damages or losses), even if such Contributor has been advised of the possibility of such damages.

9. Accepting Warranty or Additional Liability. While redistributing the Work or Derivative Works thereof, You may choose to offer, and charge a fee for, acceptance of support, warranty, indemnity, or other liability obligations and/or rights consistent with this License. However, in accepting such obligations, You may act only on Your own behalf and on Your sole responsibility, not on behalf of any other Contributor, and only if You agree to indemnify, defend, and hold each Contributor harmless for any liability incurred by, or claims asserted against, such Contributor by reason of your accepting any such warranty or additional liability.

END OF TERMS AND CONDITIONS

APPENDIX: How to apply the Apache License to your work.

To apply the Apache License to your work, attach the following boilerplate notice, with the fields enclosed by brackets "[]" replaced with your own identifying information. (Don't include the brackets!) The text should be enclosed in the appropriate comment syntax for the file format. We also recommend that a file or class name and description of purpose be included on the same "printed page" as the copyright notice for easier identification within third-party archives.

Copyright [yyyy] [name of copyright owner]

Licensed under the Apache License, Version 2.0 (the "License"); you may not use this file except in compliance with the License. You may obtain a copy of the License at

<http://www.apache.org/licenses/LICENSE-2.0>

Unless required by applicable law or agreed to in writing, software distributed under the License is distributed on an "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, either express or implied. See the License for the specific language governing permissions and limitations under the License.

OpenSSL

This product includes software developed by the OpenSSL Project for use in the OpenSSL Toolkit (<http://www.openssl.org>).

Copyright © 1998-2007 The OpenSSL Project. All rights reserved.

Copyright © 1995-1998 Eric Young (eay@cryptsoft.com). All rights reserved.

THIS SOFTWARE IS PROVIDED BY THE OPENSOURCE PROJECT "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE OPENSOURCE PROJECT BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

PHP

Copyright © 1999-2006 The PHP Group. All rights reserved.

This product includes PHP software, freely available from <http://php.net/software/>.

"THIS SOFTWARE IS PROVIDED BY THE PHP DEVELOPMENT TEAM "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE PHP DEVELOPMENT TEAM BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE."

SpyC

The MIT License

Copyright (c) 2005-2006 Chris Wanstrath

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE."

Prototype.js

Copyright (c) 2005-2007 Sam Stephenson

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

W3C

Copyright © 2008 World Wide Web Consortium, (Massachusetts Institute of Technology, Institut National de Recherche en Informatique et en Automatique, Keio University). All Rights Reserved. <http://www.w3.org/Consortium/Legal>.

JSON

Copyright (c) 2002 JSON.org

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

The above copyright notice and this permission notice shall be included in all copies or substantial portions of the Software.

The Software shall be used for Good, not Evil.

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

PNET

Copyright © 2002, Peter Bozarov All rights reserved.

THIS SOFTWARE IS PROVIDED BY THE AUTHOR "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE AUTHOR BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Bitstream Vera Font

Copyright © 2003 by Bitstream, Inc. All rights reserved. Bitstream Vera is a trademark of Bitstream, Inc.

THIS FONT SOFTWARE IS PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO ANY WARRANTIES OF MERCHANTABILITY, FITNESS AND NONINFRINGEMENT OF COPYRIGHT, PATENT, TRADEMARK, OR OTHER RIGHT. IN NO EVENT SHALL BITSTREAM OR THE GNOME FOUNDATION BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, INCLUDING GENERAL, SPECIAL, INDIRECT, INCIDENTAL, OR CONSEQUENTIAL DAMAGES, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF THE USE OR

INABILITY TO USE THE FONT SOFTWARE OR FROM OTHER DEALINGS IN THE FONT SOFTWARE.

Script.aculo.us

Copyright (c) 2005 Thomas Fuchs
(<http://script.aculo.us>, <http://miraculo.us>).

Permission is hereby granted, free of charge, to any person obtaining a copy of this software and associated documentation files (the "Software"), to deal in the Software without restriction, including without limitation the rights to use, copy, modify, merge, publish, distribute, sublicense, and/or sell copies of the Software, and to permit persons to whom the Software is furnished to do so, subject to the following conditions:

THE SOFTWARE IS PROVIDED "AS IS", WITHOUT WARRANTY OF ANY KIND, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO THE WARRANTIES OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE AND NONINFRINGEMENT. IN NO EVENT SHALL THE AUTHORS OR COPYRIGHT HOLDERS BE LIABLE FOR ANY CLAIM, DAMAGES OR OTHER LIABILITY, WHETHER IN AN ACTION OF CONTRACT, TORT OR OTHERWISE, ARISING FROM, OUT OF OR IN CONNECTION WITH THE SOFTWARE OR THE USE OR OTHER DEALINGS IN THE SOFTWARE.

PNGQuant.c

Copyright (c) 1989, 1991 Jef Poskanzer.

Copyright © 1997, 2000, 2002 by Greg Roelofs; based on an idea by Stefan Schneider.

Permission to use, copy, modify and distribute this software and its documentation for any purpose and without fee is hereby granted, provided that the above copyright notice appear in all copies and that both that copyright notice and this permission notice appear in supporting documentation. This software is provided "as is" without express or implied warranty.

Rwpng.c/Rwpng.h

Copyright © 1998-2002

Index

A

accounts
 administrator, 4-4
 database, 3-3
 operating system, 2-7
Administrator, 5-1
AJAX support, 1-9
Apache Web server, 4-1

C

client requirements, 1-9
Collector
 checking status, 5-8
 configuring, 5-5
 description, 1-5
 registering, 5-5
 resetting, 5-5
configuration
 apache, 4-1
 Collector, 5-5
 firewall, 2-5
 initial RUEI, 5-1
 MTA, 4-5
 network, 2-3
 options, 1-6
 PHP, 4-1
 post installation, 5-1
 Reporter communication, 4-5
 SELinux, 2-6
 SNMP, 4-5
cookie technology, 5-6
copy ports, 1-3

H

hardware requirements, 1-7

I

installation
 data collection, 1-1
 Linux, 2-1
 Oracle database, 3-3
 Oracle database directory, 3-4
 RUEI software, 4-2

 type, 5-3
 verifying, 4-6
installation checklist, B-1
Instant Client, 4-2

L

Linux
 date and time settings, 2-7
 disk partitioning, 2-2
 firewall configuration, 2-5
 installation, 2-1
 installer, 2-1
 package installation, 2-3
 user creation, 2-7

M

mail setup, 5-3
MTA configuration, 4-5

N

network
 requirements, 1-9
 traffic, 5-7
NTP daemon, 2-8

O

Oracle database
 init script file, 3-7
 installation, 3-3
 installation directory, 3-4
 Instant Client, 4-2
 kernel settings, 3-3
 required packages, 3-2
 shell limits, 3-4
 user accounts and groups, 3-3
 user's environment, 3-5

P

pages names, 5-6
php-oci8 module, 4-2

R

Reporter

- description, 1-5
- installation type, 5-3

requirements

- client, 1-9
- disk space, 2-2
- hardware, 1-7
- network, 1-9
- software, 1-8
- swap space, 2-3

rollbacking, 4-10

rsvg warnings, 4-2

RUEI

- client requirements, 1-9
- configuring, 5-1
- confirming data collection, 5-8
- deployment options, 1-5
- hardware requirements, 1-7
- installation checklist, B-1
- introduction, 1-1
- mail setup, 5-3
- naming pages, 5-6
- network requirements, 1-9
- post-innallation configuration, 5-6
- product architecture, 1-2
- scalability options, 1-6
- scope of monitoring, 5-6
- security, 1-2
- software requirements, 1-8
- troubleshooting, A-1
- upgrading, 4-6
- verifying, 5-7

S

security, 1-2

SELinux, 2-6

SNMP, 4-5

software requirements, 1-8

SSL keys, 5-6

T

TAPs, 1-4

third-party licenses, C-1

troubleshooting, A-1

U

upgrading, 4-6

user identification, 5-6

users

- authorizing, 5-7
- identification, 5-6
- Linux, 2-7
- Oracle database, 3-3
- Oracle database environment, 3-5

Y

Yum repository, 3-2

Z

Zend optimizer, 4-3