

The Oracle logo, consisting of the word "ORACLE" in a bold, red, sans-serif font, is centered within a thin black rectangular border.

# **Agile Product Lifecycle Management**

Database Upgrade Guide

v9.2.2.7

Part No. E15408-01

September 2009

## Copyright and Trademarks

*Copyright © 1995, 2009, Oracle and/or its affiliates. All rights reserved.*

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

### U.S. GOVERNMENT RIGHTS

Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third party content, products and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third party content, products or services.

# CONTENTS

---

Copyright and Trademarks .....	ii
<b>Preparing for the Upgrade .....</b>	<b>1</b>
Preparing the System .....	1
Database Upgrade Planning .....	1
Task Overview .....	2
Downloading the Software .....	2
Creating the Agile PLM Database Instance .....	3
Validating the Databases .....	3
<b>Understanding the Property Files .....</b>	<b>5</b>
The aut.properties File .....	5
Defining the aut.properties Parameters .....	5
Whether Source Equals Destination .....	6
Destination Details .....	6
Source Details .....	7
Averify Details .....	8
Import Warnings .....	8
Language Details .....	8
Character Set Encoding Details .....	9
File Manager Internal Locator Details .....	9
Destination Version .....	9
8.5 Only Details .....	9
The psupgrade.properties File .....	10
Defining the psupgrade.properties Parameters .....	10
The peupgrade.properties File .....	12
Defining the peupgrade.properties Parameters .....	13
<b>Upgrading the Agile PLM Database .....</b>	<b>15</b>
Running the Automated Upgrade Tool .....	15
Checking the Status of the Upgrade .....	15
What's Not Upgraded .....	15
Troubleshooting the Upgrade .....	15
Data Migration for Signoff User Dual Identification .....	18
<b>Configuring the Agile PLM Database .....</b>	<b>21</b>
Reorganizing the Database .....	21
Configuring the Agile SDK .....	22

- Configuring PG&C .....22
- Configuring PPM .....23
  - Running the PPM Post Upgrade Utility.....23
- AUT Maintenance ..... 25**
- Updating the AUT .....25
- Updating File Attachments .....25
- Running Averify .....25

# Preface

The Agile PLM documentation set includes Adobe® Acrobat PDF files. The [Oracle Technology Network \(OTN\) Web site](http://www.oracle.com/technology/documentation/agile.html) <http://www.oracle.com/technology/documentation/agile.html> contains the latest versions of the Agile PLM PDF files. You can view or download these manuals from the Web site, or you can ask your Agile administrator if there is an Agile PLM Documentation folder available on your network from which you can access the Agile PLM documentation (PDF) files.

---

**Note** To read the PDF files, you must use the free Adobe Acrobat Reader version 7.0 or later. This program can be downloaded from the [Adobe Web site](http://www.adobe.com) <http://www.adobe.com>.

---

The [Oracle Technology Network \(OTN\) Web site](http://www.oracle.com/technology/documentation/agile.html) <http://www.oracle.com/technology/documentation/agile.html> can be accessed through **Help > Manuals** in both Agile Web Client and Agile Java Client. If you need additional assistance or information, please contact [support](http://www.oracle.com/agile/support.html) <http://www.oracle.com/agile/support.html> (<http://www.oracle.com/agile/support.html>) for assistance.

---

**Note** Before calling Oracle Support about a problem with an Agile PLM manual, please have the full part number, which is located on the title page.

---

## TTY Access to Oracle Support Services

Oracle provides dedicated Text Telephone (TTY) access to Oracle Support Services within the United States of America 24 hours a day, 7 days a week. For TTY support, call 800.446.2398. Outside the United States, call +1.407.458.2479.

## Readme

Any last-minute information about Agile PLM can be found in the Readme file on the [Oracle Technology Network \(OTN\) Web site](http://www.oracle.com/technology/documentation/agile.html) <http://www.oracle.com/technology/documentation/agile.html>

## Agile Training Aids

Go to the [Oracle University Web page](http://www.oracle.com/education/chooser/selectcountry_new.html) [http://www.oracle.com/education/chooser/selectcountry\\_new.html](http://www.oracle.com/education/chooser/selectcountry_new.html) for more information on Agile Training offerings.

## Accessibility of Code Examples in Documentation

Screen readers may not always correctly read the code examples in this document. The conventions for writing code require that closing braces should appear on an otherwise empty line; however, some screen readers may not always read a line of text that consists solely of a bracket or brace.

## Accessibility of Links to External Web Sites in Documentation

This documentation may contain links to Web sites of other companies or organizations that Oracle does not own or control. Oracle neither evaluates nor makes any representations regarding the accessibility of these Web sites.



## Preparing for the Upgrade

### This chapter includes the following:

---

- Preparing the System ..... 1
- Database Upgrade Planning..... 1
- Creating the Agile PLM Database Instance..... 3
- Validating the Databases..... 3

You can upgrade your database from your currently installed version to Agile PLM 9.2.2.7 using the Automated Upgrade Tool.

The upgrade tool takes inputs from a property file and completes the upgrade using your existing database as the source database. When complete, the destination database is upgraded to the 9.2.2.7 release. Please see the AUT Release Notes for more information about supported upgrade paths for this release.

## Preparing the System

---

**Note** You should prepare a separate test environment to become familiar with the upgrade procedure.

---

If you are upgrading from an 8.5 product and your Oracle 8i home is not local to the machine where your database will be installed, you must map a local drive on the destination machine to point to the existing Oracle 8i home.

Agile PLM 9.2.2.7 supports Oracle 9i and 10g databases. You **MUST** install either Oracle 9i or 10g on the system where you are installing the Agile database before starting the upgrade. Use the instructions in the *Agile PLM Database Installation Guide* to install Oracle 9i Release 2 or Oracle 10g Release 2, if it is not already installed.

Also, if you are upgrading from an 8.5 product, you should create a new Oracle instance for the new Agile PLM product version and try to reuse the existing 8.5 Oracle instance. It is further recommended that the new Oracle instance is created on Oracle 10g to take advantage of the latest Oracle features.

You must also have JRE 1.5 installed and the JAVA\_HOME environment variable should be set with the same JRE on the system where the AUT is run.

## Database Upgrade Planning

The entire upgrade process may take a considerable amount of time depending on the size of the database and the hardware configuration. Based on past experience, 75% of the upgrade process is spent on upgrading and backing up the database. We strongly recommend running the schema backup and upgrade on a test system so that appropriate time can be scheduled for the production deployment.

There are two types of upgrade:

- **Upgrade destination in place** - Source database is upgraded with the existing database user. In the *aut.properties* file, the parameter `sourceEqualsDestination` is set to true.
- **Upgrade source to destination** - A new database user is created in the destination database instance using *useragile.sql*, and then the source database is upgraded to that user. In the *aut.properties* file, the parameter `sourceEqualsDestination` is set to false.

## Task Overview

The sequence of actions to be performed for an upgrade is as follows:

1. Undeploy the Agile PLM application.
2. Upgrade the database to 9.2.2.7:
  - a. Download the Agile PLM database installer and Automated Upgrade Tool (AUT). For instructions, see [Downloading the Software](#) on page 2.
  - b. Configure and run AUT. For instructions on configuring AUT for each type of upgrade, see [Understanding the Property Files](#) on page 5 and [Whether Source Equals Destination](#) on page 6.
  - c. Generate maintenance scripts for the target release:
    - For Windows, run the database installer with the **Generate database scripts only** option selected. For details, see the *Agile PLM Database Installation* guide.
    - For UNIX, run `agile9dbscripts.sh`
  - d. Reorganize the database as described in [Reorganizing the Database](#) on page 21.
3. Install the Agile PLM application software.
4. Deploy the Agile PLM application.

## Downloading the Software

The Automated Upgrade Tool is distributed with each Agile major release and subsequent service pack releases. The software can be downloaded from [Oracle E-Delivery](#) (<http://edelivery.oracle.com>) or [Oracle Metalink](#) (see Oracle Metalink - <https://metalink.oracle.com>).

### To download the software from Oracle E-Delivery:

1. On the Oracle E-Delivery Welcome page, choose your language and click **Continue**.
2. Enter required information on the Export Validation screen and click **Continue**.
3. On the Search screen, select **Oracle Agile Applications** in the **Select a Product Pack** drop-down list box. Select a platform value. Click **Go**.
4. Links to applicable Agile release downloads display. Select the appropriate link. Click **Continue**.
5. The Download screen displays downloadable release parts, including customer guides. Click **Download** for the appropriate media pack.
6. Extract the contents of the media pack. The Agile PLM Database Installer is included with the Agile PLM software.
7. To download the database installer, navigate to the **DBInstaller** folder within the **Database** folder. DB installers for all platforms are made available within the **DBInstaller** folder, regardless of the

operating system on which you have chosen to install Agile PLM.

8. To download the AUT software, navigate to the **AUT** folder within the **Deployment\_Tools** folder. From the AUT folder, extract the contents of the *AUT.zip* file to your destination database server. After the AUT is extracted, all of the files are located in an AUT directory on the local drive. In this document, this directory is referred to as the **AUT\_HOME**.

#### **To download the software from Oracle Metalink:**

1. Log in and select the **Classic MetaLink** option.
2. To download the Agile PLM media pack, perform a simple search:
  - a. In the **Search By** field, search by **Product or Family**, and select **Agile Product Lifecycle Management** from the list.
  - b. Select appropriate values for the **Release** and **Platform and Language** fields, and click **Go**.
  - c. Click the **Download Now** icon to download the media pack.
3. To download the AUT software only, change the selection in the **Release** field to **Agile PLM Tools** and click **Go**.
4. Download the appropriate AUT version. From the Patchset zip file, extract the contents of the *AUT.zip* file to your destination database server. After the AUT is extracted, all of the files are located in an AUT directory on the local drive. In this document, this directory is referred to as the **AUT\_HOME**.

## **Creating the Agile PLM Database Instance**

Unless you plan to upgrade in-place, a new database instance must be created before you can upgrade your existing database. This database instance will be used as the destination database during the upgrade process.

To create the Agile PLM 9.2.2.7 database instance, follow the instructions in the *Agile PLM Database Installation Guide*, based on your specific operating system.

After the 9.2.2.7 database instance is created, run the *useragile.sql* script, located in the `$AUT_HOME\scripts\Oracle\utilities\script_tools` directory, to create a new, empty user in the database.

---

**Note** Change the token values inside of the @ symbols in the *useragile.sql* file before running the script.

---

## **Validating the Databases**

You should validate the source and destination databases to ensure a successful upgrade by performing the following checks:

- Run the latest *averify* script on the source database and fix any errors.

- For each database upgrade, you should know the following:
  - Source and destination database user and password
  - Destination system user and password
  - TNS configuration for source and destination database on the respective database systems
  - Paths to the Oracle Homes
- Map the source and destination Oracle Homes, if necessary.
- Validate the TNS entries of the source and destination databases.

On a command line, change ORACLE\_HOME to point to the Oracle Home of the source database, then try to connect to it using the TNS name. Repeat this procedure for the destination database.

- Make sure the destination database user exists and there are no objects in the schema.

---

**Note** This does not apply if your source database is also your destination database.

---

- Make sure the source and destination database users have the same roles and privileges.
- Make sure the Agile tablespaces in the destination and source databases match. Also, the destination database should have unlimited tablespace.
- Verify that the available tablespace in the destination database is sufficient to complete the database upgrade.

# Understanding the Property Files

**This chapter includes the following:**

---

▪ The aut.properties File.....	5
▪ Defining the aut.properties Parameters .....	5
▪ The psupgrade.properties File .....	10
▪ The peupgrade.properties File.....	12

AUT uses property files to supply the input information to the database scripts. If you are not upgrading a Product Cost Management 8.5 or Program Execution 8.5 database, you should only complete the aut.properties file. If you are also upgrading a Product Cost Management 8.5 or Program Execution 8.5 database, you should complete either the psupgrade.properties file or the peupgrade.properties file, in addition to the aut.properties file.

## The aut.properties File

The aut.properties file, located in the \$AUT\_HOME\config directory, contains user-supplied information on the source and destination databases. The source database parameters contain information about the database to be upgraded. The destination database parameters contain information about the user and host details of the database where the source database is being upgraded. These parameters are used by the database scripts during the upgrade process.

## Defining the aut.properties Parameters

You can edit the **aut.properties** file to define parameters such as:

- Whether Source Equals Destination
- Destination Details
- Source Details
- Averify Details
- Import Warnings
- Language Details
- Character Set Encoding Details
- File Manager Internal Locator Details
- Destination Version
- 8.5 Only Details

Each parameter is followed by an example displaying the correct format for each parameter value. You must complete the source and destination details in order for AUT to proceed with the upgrade.

## Whether Source Equals Destination

Parameter	Value Definition
sourceEqualsDest	<p>Determines if the source database is upgraded to the destination database with or without the database user.</p> <p>If this value is set to <b>true</b> (upgrade destination in-place):</p> <ul style="list-style-type: none"> <li>▫ the source database is upgraded without exporting and importing the database user to the destination database. This means that the existing database user is upgraded instead of importing to a new database user and then upgrading.</li> </ul> <p><b>Note</b> This does NOT apply if your source and destination databases are on different versions of the Oracle database.</p> <ul style="list-style-type: none"> <li>▫ AUT does not perform an export unless a value for the <code>src.db.backup</code> parameter is specified.</li> <li>▫ the source database details are not required.</li> <li>▫ no values need to be provided for the following destination parameters: <ul style="list-style-type: none"> <li>• <code>dest.db.system.user</code></li> <li>• <code>dest.db.system.password</code></li> </ul> </li> </ul>

## Destination Details

Parameter	Value Definition
dest.jdbc.url	The JDBC connection string to the destination database. The format is <code>jdbc:oracle:thin@&lt;DESTINATION_DB_HOST_NAME&gt;:&lt;PORT&gt;:&lt;SID&gt;</code> where <code>DESTINATION_DB_HOST_NAME</code> is the hostname of the destination database, <code>PORT</code> is the listener port of the destination database (1521 is the default), and <code>SID</code> is the database instance.
dest.jdbc.driver	The database driver of the destination database. The default is <code>oracle.jdbc.driver.OracleDriver</code> .
dest.db.user	The database user of the destination database.
dest.db.password	The encrypted database password of the destination database. Use the <code>encryptpwd</code> utility located in the <code>\$AUT_HOME\bin</code> directory to encrypt the password.
dest.db.system.user	The user of the system account on the destination database instance.
dest.db.system.password	The encrypted password of the system user account on the destination database instance.
dest.tns.name	The TNS entry name in the Oracle Home of the destination database.

Parameter	Value Definition
dest.oracle.home	<p>The Oracle Home of the destination database. This value can be a mapped drive on the system where the AUT is run which points to the shared folder on the host machine.</p> <hr/> <p><b>Note</b> Use either double back slashes or a forward slash for directory separation, for example, d:/oracle/ora92.</p> <hr/>
sourceEqualsDest	<p>Determines if the source database is upgraded to the destination database with or without the database user. If true, then the source database is upgraded without exporting and importing the database user to the destination database. This means that the same user is upgraded instead of upgrading to a different user on the destination database. This does NOT apply if your source and destination databases are on different versions of the Oracle database. Also, when this value is set to true, the AUT does not import and export unless a value for the src.db.backup parameter is specified.</p> <p>If this parameter is set to true, the following destination database details are not required:</p> <ul style="list-style-type: none"> <li>•dest.jdbc.url</li> <li>•dest.jdbc.driver</li> <li>•dest.db.user</li> <li>•dest.db.password</li> </ul>

## Source Details

Parameter	Value definition
src.jdbc.url	The JDBC connection string to the source database. The format is <b>jdbc:oracle:thin@&lt;SOURCE_DB_HOST_NAME&gt;:&lt;PORT&gt;:&lt;SID&gt;</b> where <b>SOURCE_DB_HOST_NAME</b> is the hostname of the source database, <b>PORT</b> is the listener port of the source database (1521 is the default), and <b>SID</b> is the database instance.
src.jdbc.driver	The database driver to use for JDBC connections to the source database. The default is oracle.jdbc.driver.OracleDriver.
src.db.user	The database user in the source database.
src.db.password	The encrypted database password of the source database. Use the encryptpwd utility located in the \$AUT_HOME\bin directory to encrypt the password.
src.tns.name	The TNS name for the source database.

Parameter	Value definition
src.oracle.home	<p>The Oracle Home of the source database. This value can be a mapped drive on the system where the AUT is run which points to the shared folder on the host machine.</p> <p><b>Note</b> Use either double back slashes or a forward slash for directory separation, for example, d:/oracle/ora102 or D:\oracle\ora102.</p>
src.db.backup	<p>Back up or do not back up the database into a dump file. If true, then the source database is backed up by exporting the database user into a dump file located at \$AUT_HOME\workingdir\AgileSrcDbBackup.dmp. If you are also upgrading a Product Cost Management or Program Execution database, their respective dump files are named Agile85pcmBACKUP.dmp and Agile85peBACKUP.dmp.</p>

**Note** If you are upgrading from Product Cost Management or Program Execution only, leave all Source detail properties blank in the aut.properties file.

## Averify Details

Parameter	Value Definition
averify.error.count	<p>Specifies the number of averify errors to occur before the AUT stops the upgrade.</p> <p>Specify <b>-1</b> to ignore the errors and continue with the upgrade.</p> <p>Specify <b>+1</b> to stop the upgrade if an error occurs. Once you fix the error, you can run AUT again to continue the upgrade.</p>

## Import Warnings

Parameter	Value Definition
ignore.imp.warnings	<p>Decide if the AUT ignores the import warnings or not while importing the database. If set to true, the warnings are ignored.</p> <p>AUT will stop if there is a critical error.</p>

## Language Details

Parameter	Value Definition
i18n.lang	<p>Specifies the language of the operating system where the database is located. The values are English, Japanese, Chinese, or French.</p>

## Character Set Encoding Details

Parameter	Value Definition
nls.lang	Specifies the character set encoding being used during database import and export. For example, AMERICAN_AMERICA.UTF8.

## File Manager Internal Locator Details

Parameter	Value Definition
file.manager.internal.locator	Specifies the location of the file manager. The content_url column in the files table is upgraded with an encrypted URL based on the file type. This URL is used after upgrading for full text search configuration. The format is <a href="http://&lt;FILE_MANAGER_HOST&gt;:&lt;PORT&gt;/Filemgr/AttachmentServlet">http://&lt;FILE_MANAGER_HOST&gt;:&lt;PORT&gt;/Filemgr/AttachmentServlet</a> .

## Destination Version

Parameter	Value Definition
dest.version	The version of the upgraded Agile PLM database.

## 8.5 Only Details

Parameter	Value Definition
isPC	Each of the parameters must have a value if the source database is either 8.5 or 8.5 SPx only. Set the parameter to true for the components that are installed on the source database and to false for the components that are not installed.
isPSI	
isPCM	
isPE	
username.migration.action	<p>Determine how you want the Agile users in the source database to appear in the destination database. The value is set as the number of one of the following choices:</p> <ol style="list-style-type: none"> <li>1. FIRSTNAME LASTNAME</li> <li>2. LASTNAME FIRSTNAME</li> <li>3. FIRSTNAME, LASTNAME</li> <li>4. LASTNAME, FIRSTNAME</li> <li>5. None of the above. FIRSTNAME will be migrated to LASTNAME.</li> </ol> <p>If your database contains mixed cases, choose the option that reflects the format for most of your users. The remaining users must be migrated manually after the upgrade.</p>

Parameter	Value Definition
gmt.timezone.difference	The GMT time zone of your database. The database and Agile application server must be on the same GMT time zone. The GMT time zone format is six characters, (+ or -)hh:mm, for example, GMT would be -00:00.
dest.users.timezone	The timezone to be used for the upgraded database. A text file listing the time zones that are supported is provided in the <b>&lt;AUT_HOME/config</b> directory . Each timezone has a corresponding ID. Enter the ID that corresponds to the applicable time zone as the value for this parameter.
dest.users.encode.type	The encode type to be used for the upgraded database. All the supported encode types are specified in comments immediately above this parameter in the <i>aut.properties</i> file. Each encode type has a corresponding ID number. Enter the ID number that corresponds to the applicable encode type as the value for this parameter.  For example, to set the default encode type to Unicode (UTF-8), set <code>dest.users.encode.type= 5</code>

## The psupgrade.properties File

The psupgrade.properties file, located in the \$AUT\_HOME\config directory, contains user-supplied information on the existing Product Cost Management database. During an upgrade of a Product Cost Management database, the data is merged into the Agile PLM database. The parameters in the file are used by the database scripts during the upgrade process to determine how the data is migrated. This file should be completed in addition to the aut.properties file if you are migrating a Product Cost Management database.

It is recommended to perform a test upgrade of the Product Cost Management database with reports to evaluate the database and make any necessary corrections before performing the actual data migration.

## Defining the psupgrade.properties Parameters

Parameter	Value Definition
pcm.jdbc.url	The JDBC connection string to the Product Cost Management database. The format is <b>jdbc:oracle:thin@&lt;SOURCE_DB_HOST_NAME&gt;:&lt;PORT&gt;:&lt;SID&gt;</b> where <b>SOURCE_DB_HOST_NAME</b> is the hostname of the Product Cost Management database, <b>PORT</b> is the listener port of the database (1521 is the default), and <b>SID</b> is the database instance.
pcm.jdbc.driver	The database driver of the Product Cost Management database. The default is oracle.jdbc.driver.OracleDriver.
pcm.db.user	The database user of the Product Cost Management database.

Parameter	Value Definition
pcm.db.password	The encrypted database password of the Product Cost Management database. Use the encryptpwd utility located in the \$AUT_HOME\bin directory to encrypt the password.
pcm.tns.name	The TNS entry name in the Oracle Home of the source database.
pcm.oracle.home	<p>The Oracle Home of the Product Cost Management 8.5 database.</p> <p><b>Note</b> Use either double back slashes or a forward slash for directory separation, for example, d:/oracle/ora92.</p>
generate.pcm.reports	<p>Set this parameter to true to generate a report about the data contained in the Product Cost Management database before migration. The report will display data matching the following rules:</p> <ul style="list-style-type: none"> <li>▫ Update firstname, lastname, and user organization for the matched user login ID, if you set the update.matched.user.data parameter to true.</li> <li>▫ Migrate the Product Cost Management Items not found in Agile 8.5, if you set the migrate.pcm.items.not.found.in.pc parameter to true.</li> <li>▫ Convert all manufacturer names to uppercase, if you set the convert.mfrName.to.upperCase parameter to true.</li> <li>▫ Update all Agile 8.5 manufacturer data with the Product Cost Management manufacturer data for the same manufacturer, if you set the update.matched.mfr.data parameter to true.</li> <li>▫ Migrate Product Cost Management manufacturer parts not found in Agile 8.5, if you set the migrate.pcm.mpns.not.found.in.pc to true.</li> </ul> <p>If you set this parameter to false, migration will proceed without a report being generated.</p> <p>If you choose to have a report generated, AUT will stop. After viewing the report and you are satisfied with the results, change this parameter to false and run AUT again.</p>
report.folder.location	Location where you want the report to be generated.
update.matched.user.data	If set to true, the firstname, lastname, and user organization are updated based on matching users in the Agile 8.5 database.
migrate.pcm.items.not.found.in.pc	If set to true, all Product Cost Management items not found in the Agile 8.5 database are migrated.
convert.mfrName.to.upperCase	If set to true, all manufacturer names are converted to uppercase.
migrate.pcm.mpns.not.found.in.pc	If set to true, all Product Cost Management manufacturer parts not found in the Agile 8.5 database are migrated.
update.matched.mfr.data	If set to true, all Agile 8.5 manufacturer data is updated with the Product Cost Management data for the same manufacturer.

Parameter	Value Definition
expiry.date.to.remove.prices	Removes prices based on the entered expiration date. All prices previous to the entered date are removed. If no date is entered, the prices are checked against the current date. Enter a date in the following format: MM-DD-YYYY.
migrate.suppliers.with.autonumber	If set to true, all suppliers are given autonumbers. If set to false, you must provide a supplier code map file and add its location to the supplier.code.crossref.filepath parameter.  The file should be in the form of comma separated text file with the heading in the first line as  supplierName,supplierCode  Agile,agil  EMS1,emsCode1
supplier.code.crossref.filepath	Location of the supplier code map file.
iFS Details*	
copy.files	If set to true, the file attachments are copied.
src.ifs.folder	The mapped drive location of the local iFS files folder.
src.ifs.schema	The database user of the Product Cost Management database.
dest.ifs.folder	The path where the upgraded file vault will be located.
dest.ifs.schema	The database user of the destination database.
*After the database is upgraded, you will need to run the IFS Reorganization tool to restructure the file vault to match the current format. For more information on this tool, see the Installation Guide.	

## The peupgrade.properties File

The peupgrade.properties file, located in the \$AUT\_HOME\config directory, contains user-supplied information on the existing Program Execution database. During an upgrade of a Program Execution database, the data is merged into the Agile PLM database. The parameters in the file are used by the database scripts during the upgrade process to determine how the data is migrated. This file should be completed in addition to the aut.properties file if you are migrating a Program Execution database.

It is recommended to perform a test upgrade of the Program Execution database with reports to evaluate the database and make any necessary corrections before performing the actual data migration.

## Defining the `peupgrade.properties` Parameters

Parameter	Value Definition
<code>pe.jdbc.url</code>	The JDBC connection string to the Program Execution database. The format is <code>jdbc:oracle:thin@&lt;SOURCE_DB_HOST_NAME&gt;:&lt;PORT&gt;:&lt;SID&gt;</code> where <b>SOURCE_DB_HOST_NAME</b> is the hostname of the Program Execution database, <b>PORT</b> is the listener port of the database (1521 is the default), and <b>SID</b> is the database instance.
<code>pe.jdbc.driver</code>	The database driver of the Program Execution database. The default is <code>oracle.jdbc.driver.OracleDriver</code> .
<code>pe.db.user</code>	The database user of the Program Execution database.
<code>pe.db.password</code>	The encrypted database password of the Program Execution database. Use the <code>encryptpwd</code> utility located in the <code>\$AUT_HOME/bin</code> directory to encrypt the password.
<code>pe.tns.name</code>	The TNS entry name in the Oracle Home of the Program Execution database.
<code>pe.oracle.home</code>	The Oracle Home of the Program Execution database.  Use either double back slashes or a forward slash for directory separation, for example, <code>d:/oracle/ora92</code> .
<code>create.del.subclass</code>	If set to true, the Deliverables subclass will be created after upgrade for data currently in that subclass. If set to false (default, the data currently in the Deliverables subclass will be migrated to the Tasks subclass after upgrade.
<code>generate.pe.reports</code>	If set to true, a report on any circular dependencies in the data is generated and no data is migrated. If set to false, no report is generated and the data is migrated.  If you choose to have a report generated, AUT will stop. After viewing the report and correcting the dependencies, change this parameter to false and run AUT again.
<code>report.folder.location</code>	Location where you want the report to be generated.
<code>pe.weekend.days</code>	Comma-separated numbers representing the weekend days in a week. The default days are Saturday and Sunday. Format: 1,7
<code>currency.description</code>	Base currency. The default is US Dollars (USD).
iFS Details*	
<code>copy.files</code>	If set to true, the file attachments are copied.
<code>src.ifs.folder</code>	The mapped drive location of the local iFS files folder.
<code>src.ifs.schema</code>	The database user of the Program Execution database.
<code>dest.ifs.folder</code>	The path where the upgraded file vault will be located.
<code>dest.ifs.schema</code>	The database user of the destination database.
*After the database is upgraded, you will need to run the IFS Reorganization tool to restructure the file vault to match the current format. For more information on this tool, see the Installation Guide.	



# Upgrading the Agile PLM Database

This chapter includes the following:

---

- Running the Automated Upgrade Tool ..... 15
- Checking the Status of the Upgrade ..... 15
- What's Not Upgraded ..... 15
- Troubleshooting the Upgrade ..... 15
- Data Migration for Signoff User Dual Identification ..... 18

## Running the Automated Upgrade Tool

**Before running the AUT:**

- Make sure you have completed all of the pre-requisites listed under Preparing for the Upgrade.
- On UNIX, change the user permissions on all of the files under AUT\_HOME in order for the upgrade log files to be created and the shell scripts under AUT\_HOME/bin to be run.
- Edit the property file with the correct values for your upgrade. See [Understanding the Property Files](#) on page 5 for more information.

**To run the AUT:**

Go to the \$AUT\_HOME\bin directory and run the aut.bat (Windows) or aut.sh (UNIX) script.

## Checking the Status of the Upgrade

You can monitor the status through the log files that are generated during the upgrade. The \$AUT\_HOME\logs directory contains all of the upgrade-related log files. AUT.log is the main log file for the upgrade. Separate directories are created for the logs generated by averify and the database scripts. These log files are located in the averifylogs and oracle subdirectories.

## What's Not Upgraded

Markup restrictions that were enforced through privileges are not retained when you upgrade. With the new security model implemented in 9.2.2.2, **Markup** is a subclass under the **File Folders** class and all markup privileges are automatically enabled. To prevent users from viewing or modifying the existing markups, you must *disable* blanket privileges at File Folders class level in Java Client and *enable* Markup privilege for relevant users only.

## Troubleshooting the Upgrade

The following list describes some problems that can occur during the database upgrade:

**What if I can't resolve my TNS service name?**

If the TNS service name cannot be resolved, then the service name specified in the aut.properties file is not correctly defined in the tnsnames.ora file.

Perform the following checks to fix the error:

- Verify that a tnsnames.ora file exists and is in the correct place. See your Oracle documentation for more information on the required name and location.
- Verify that the service name exists in one of the tnsnames.ora files. Add the service name, if necessary.
- Make sure there are no syntax errors in the tnsnames.ora file, especially unmatched parentheses or stray characters.

**Why did I receive an Invalid User Name or Password error in the AUT.log file?**

You may receive this error if the database connection was not successful. The following Oracle error messages may be displayed:

**EXP-00004: invalid username or password**

**Cause:** An invalid username or password was specified.

**Action:** Retry with a valid username and password.

**ORA-01017: invalid username/password; logon denied**

**Cause:** An invalid username or password was entered in an attempt to log on to Oracle. The username and password must be the same as was specified in a GRANT CONNECT statement. If the username and password are entered together, the format is username/password.

**Action:** Enter a valid username and password combination in the correct format.

**What errors would I see if an import fails?**

An import can end abnormally due to some of the following reasons:

**IMP-00009: abnormal end of export file**

**Cause:** The export file is probably from an aborted Export session.

**Action:** If so, retry the export and import.

**IMP-00013: only a DBA can import a file exported by another DBA**

**Cause:** The privileges needed to import an export file generated by a database administrator do not exist. Only a database administrator can import such files.

**Action:** The source and destination database users should have the same roles and privileges. Because the source database has the DBA role, the database destination should also have the role. If you do not want the destination database to have the DBA role, then remove the role from the source database and retry the upgrade.

**IMP-00041: Warning: object created with compilation warnings**

**Cause:** The object in the SQL statement following this error was created with compilation errors. If this error occurred for a view, it is possible that the base table of the view was missing or altered.

**Action:** This is a warning. The object may have to be recompiled before being used.

**Why is AUT hanging?**

AUT may not be hanging. Processes may be running that seem to take longer than others. For example:

- Indexes may be missing on the source database. If this is the case, averify may be running slowly.
- The import may be taking a longer time because it's a large database.

**What should I do if AUT suddenly exits?**

Check the AUT.log file. If no information is available, then the AUT could not start because of invalid settings. Check the pre-requisites and the contents of the aut.properties file before retrying.

**If I have database connection problems, what Oracle errors will I get?**

Database connection errors can occur if the SQL connection to the source or destination database is lost. Make sure that the database connections are available before running the AUT. If connection problems occur, you may see some of the following Oracle error messages:

**ORA-01034: ORACLE not available**

**Cause:** Oracle was not started. Possible causes include the following:

- The SGA requires more space than that was allocated for it.
- The operating system variable pointing to the instance is improperly defined.

**Action:** Refer to accompanying messages for possible causes and correct the problem mentioned in the other messages. If Oracle has been initialized, then on some operating systems, verify that Oracle was linked correctly.

**ORA-01089: immediate shutdown in progress - no operations are permitted**

**Cause:** The SHUTDOWN IMMEDIATE command was used to shut down a running Oracle instance, terminating any active operations.

**Action:** Wait for the instance to be restarted or contact the database administrator.

**ORA-01090: shutdown in progress - connection is not permitted**

**Cause:** The SHUTDOWN command was used to shut down a running Oracle instance, disallowing any connects to Oracle.

**Action:** Wait for the instance to restart or contact the database administrator.

**ORA-12541: TNS: no listener**

**Cause:** The connection request could not be completed because the listener is not running.

**Action:** Ensure that the supplied destination address matches one of the addresses used by the listener - compare the tnsnames.ora entry with the appropriate listener.ora file (or tnsnav.ora if the connection is by way of an interchange). Start the listener on the remote machine.

**I received an ORA-00955 error in my AUT.log file. What should I do?****ORA-00955: name is already used by an existing object**

**Cause:** An attempt was made to create a database object (such as a table, view, cluster, index, or synonym) that already exists. A user's database objects must have distinct names.

**Action:** Enter a unique name for the database object or modify or drop the existing object so it

can be reused.

You can ignore this in the Agile schema because the object already exists. The upgrade process takes care of dropping the object and recreating it if there are any changes.

I received an ORA-00904 error. What should I do?

**ORA-00904: MS\_JAVA "."."LONGNAME":Invalid Identifier.**

**Solution:** Log in as the **sys** user and run the `$ORACLE_HOME\javavm\install\initdbj.sql` script.

I received an ORA-01555 error. What should I do?

**ORA-01555: "snapshot too old (rollback segment too small" when using Automatic Undo Management (AUM).**

**Solution:** The UNDO tablespace is too small. Increase the size of the UNDO tablespace. Note that the UNDO tablespace should be large enough to store the undo data generated by active transactions as well as those preserved to honor the undo retention setting.

Increase the value of the `Undo_retention` parameter. This is important for systems running long queries. The parameter's value should at least be equal to the length of the longest running query on a given database instance. This can be determined by querying the `V$UNDOSTAT` view once the database has been running for a while:

```
SQL> select max (maxquerylen) from v$undostat;
```

How long does it take the AUT to run?

The amount of time it takes the AUT to run depends on the database size. The amount of time needed to upgrade is also based on the database version of the source database. Import and export steps can be avoided by using the `sourceEqualsDest` property which also reduces the time.

## Data Migration for Signoff User Dual Identification

Agile provides optional data migration scripts that can be used by customers who choose to implement the Signoff User Dual Identification feature for approval signoffs. The Signoff User Dual Identification feature was introduced to address FDA regulations laid out in 21 CFR Part 11 Section 11.200. The system now facilitates the usage of two forms of identification from the user when signing off on a document such as a change order.

If the Login Password is to be used as a second form of identification, the following scripts can be used to automate the required administration procedures.

Details of these scripts and the actions they perform are provided in the following table:

#	Script	Action
1.	<b>UseLoginPwdYesList.bat</b>	Identifies the list of users who have set the "Use Login Password for Approval" option to <b>Yes</b> in Preferences and writes the output to a comma separated (.csv) file.  <b>Note</b> The default filename for the output file is <code>Output.csv</code> . To change the filename, suffix a filename to the command as shown: <code>UseLoginPwdYesList &lt;FileName&gt;</code> . Where

#	Script	Action
		<FileName> is the name of the .csv file.
2.	<b>ChangeUseLoginPwdToNo.bat</b>	Resets the "Use Login Password for Approval" option to <b>No</b> for all users who have set it to <b>Yes</b> in Preferences.
3.	<b>LoginPwdAppPwdMatchList.bat</b>	Identifies the list of users who have identical Login and Approval passwords and have set the "Use Login Password for Approval" option to <b>No</b> . Writes the output to a .csv file.
4.	<b>SetApprovalPwd.bat</b>	Resets the approval passwords to an administrator-supplied value for users who have identical Login and Approval passwords and have set the "Use Login Password for Approval" option to <b>No</b> . To change the password, suffix the new password value to the command as shown: <b>SetApprovalPwd &lt;password&gt;</b> . Where <password> is the new value for the approval password. (The password is in cleartext.)

**To migrate data to meet second signature requirements:**

1. Locate the second signature migration scripts stored at the following path:  
**<Agile installation folder>/ agileDomain/tools/ SecondSignature.zip**
2. Unzip the **SecondSignature.zip** file and extract the scripts to a new folder (temp directory) in the same location.
3. Run each bat/shell file in the sequence listed in the table above.

---

**Note** For Solaris/Linux installations, the corresponding **.sh** files are provided. You may have to change the format of the script files from DOS to UNIX.

---

Once approval passwords have been reset, users should be asked to change the administrator-provided approval password to a password of their choice. (This should not be the same as the login password.)



# Configuring the Agile PLM Database

## This chapter includes the following:

- Reorganizing the Database ..... 21
- Configuring the Agile SDK ..... 22
- Configuring PG&C ..... 22
- Configuring PPM..... 23

After the Agile PLM database has been configured and all verify errors have been fixed, you must run additional database scripts to reorganize the database and to enable Full Text Search in the Agile PLM 9.2.2.7 database.

## Reorganizing the Database

**Important** The Agile PLM 9.2.2.7 database includes two user accounts, CTXSYS and AGILE. The following upgrade procedure is required for the database sizing and configuration of the CTXSYS and AGILE accounts.

After AUT is run, the upgraded schema and data have been validated. However, the data still needs to be analyzed and statistics generated to enable Cost-Based optimizer (CBO) and Full Text Search (FTS) support. There are eight Agile-specific tablespaces required for optimization. The Agile schema has to be reorganized for this optimization to occur.

### To reorganize the upgraded schema:

1. On the database server, change to the following directory:
  - (Windows) `\oracle\admin\<Oracle SID>\create\<agile schema user>`
  - (UNIX) `$ORACLE_BASE/admin/$ORACLE_SID/create/agile`
2. Run the **agile9exp** script.
 

The `agile9exp.dmp` file is created in the current folder. This dump file is used with the `agile9imp` script. Make sure the dump file can be imported successfully before proceeding to the next step.
3. Run the **recreateagile** script to drop the existing account and recreate the agile account and schema.
4. Run the **agile9imp** script to import the upgraded Agile schema, including setup of CBO and FTS.
5. Rename the existing `agile9exp.dmp` file to `agile9exp_upgrade9227.dmp` for backup. Also rename the `agile9exp.log` file to `agile9exp_upgrade9227.log`.
6. Run the **agile9exp** script again.
 

The `Agile9exp.dmp` file created can be used as a backup of the system after the Agile PLM 9.2.2.7 database reorganization.
7. Rename the `agile9exp.dmp` file to `agile9exp_reorg9227.dmp` for backup. Also rename the

agile9exp.log file to agile9exp\_reorg9227.log.

8. Start SQL\*Plus from a command line and log in as **agile/tartan** or **agile/tartan@<Oracle SID>**.
9. Run the agile9\_check.sql file to validate the schema integrity and confirm integrity of the database reorganization.

**SQL> @agile9\_check.sql**

---

**Note** If errors are displayed, contact [support](http://www.oracle.com/agile/support.html) <http://www.oracle.com/agile/support.html>. All errors must be fixed before proceeding to the next step.

---

10. Start the Oracle listener.

---

**Note** The following steps should only be performed after you have upgraded the Agile PLM application:

---

11. Start the Agile application server.
12. Shut down the database.
13. Perform a cold backup of all the database-related files.
14. Restart the database, listener, and application server.

## Configuring the Agile SDK

If you are using the Agile SDK, delete the **AgileSDK.cache** directory from your client machines after you have upgraded the Agile PLM database and application server. The **AgileSDK.cache** directory is found under the **temp** directory (%temp%AgileSDK.cache).

## Configuring PG&C

If you have the PG&C component installed, additional configuration may be needed for substance migration.

Substance migration is necessary if you have met ALL of the following requirements:

- Upgraded your database from Agile PLM 9.2 to Agile PLM 9.2.2.7.
- Imported the JGPSSI substances and substance groups.

---

**Note** In Agile PLM 9.2.2.7, you should use IPC declarations with IPC substances and substance groups. Note that the IPC list of substances and substance groups is slightly different than the JGP list of substances and substance groups.

---

**Important** Contact your Agile Solutions Delivery representative to obtain the files needed for substance migration.

If you imported the JGPSSI substances in Agile PLM 9.2, but do not want to use the IPC substances, you can continue to use the JGPSSI substances without migrating.

## Configuring PPM

With PPM objects, there should always be at least one user in the team, such as Owner. For every user on the team, a corresponding Access Control List (ACL) in the Share should exist. In the 9.0 and 9.1 releases of Agile PLM, a logged in user was allowed to delete all users from Share which included the owner's ACL.

You must clean the corrupted data in the ObjectACL database table to access the shared objects. The data cleanup involves replacing the deleted role with a valid, non-deleted equivalent role. The following SQL statement cleans all of the corrupted rows in ObjectACL table where a deleted role is assigned to a user with the valid role:

```
DELETE FROM TEAM WHERE ACTIVITY_ID<=0;
INSERT INTO OBJECTACL SELECT TEAM.activity_id, (SELECT CLASS FROM
ACTIVITY WHERE
id=TEAM.activity_id),TEAM.user_id, ',9506,',sysdate,sysdate FROM TEAM
WHERE TEAM.user_id NOT IN (SELECT USERID FROM OBJECTACL WHERE
OBJECTACL.objid=TEAM.activity_id AND OBJECTACL.objclass IN
(18022,18387))
```

In the previous SQL statement, the Program Team Member role is generally assigned to a user and the ID for this out-of-box role is 9506.

The roleid values may differ if you have customized your database. In this case, use the following SQL statement to obtain roleid values for each role in your database:

```
select ID from nodetable where parentid=5006 and value = '<name of
role>';
```

The Agile Administrator is still allowed to delete a role assigned to a user in the object's ACL. If a role is deleted, an error message stating "Node <number> does not exist in cache." displays when the object is accessed.

Also, in earlier releases of Agile PLM, the Dashboard or other PPM-related home pages were allowed to be selected as the start page. In Agile PLM 9.2.2.1, a license check was added for default home pages. If any users have previously set their preferred Start Page and preferred Inbox to values that are related to PPM objects and PPM is no longer installed, run the following SQL statements to set the pages:

**To set the Preferred Start Page to Home for all users:**

```
update agileuser set PREFSTARTPAGE=1;
```

**To set the Preferred Inbox View to Notifications if the Preferred Inbox View is Activities**

```
update agileuser set PREFINBOXVIEW=3 where PREFINBOXVIEW=2;
```

## Running the PPM Post Upgrade Utility

After you have upgraded your database and installed the Agile PLM 9.2.2.7 application, you must run the PPM Post Upgrade Utility to accommodate the business rule changes introduced in this new version. For information on how to run this utility, see the *Agile PLM Installation Guide* for your specific application server.



## AUT Maintenance

**This Appendix includes the following:**

---

- Updating the AUT ..... 25
- Updating File Attachments..... 25
- Running Averify ..... 25

Before you upgrade your database, you should always make sure you are using the latest version of the AUT. Changes to scripts such as averify may occur after the initial version has been released. To ensure your database is correctly upgraded, always check the [Oracle Metalink](https://metalink.oracle.com) (see Oracle Metalink - <https://metalink.oracle.com>) website for updates.

### Updating the AUT

If updates are needed to the AUT, you can always find the latest version on [Oracle Metalink](https://metalink.oracle.com) (see Oracle Metalink - <https://metalink.oracle.com>). Download the AUT.zip file and extract the file contents into the same directory where you originally extracted the files.

### Updating File Attachments

If the `file.manager.internal.locator` property was not specified in the `aut.properties` file during upgrade, searches for attachment content in Agile PLM may not return up-to-date results, as the `content_url` column in the database is not updated.

To update the `content_url` column anytime after the database upgrade, specify this location in the `aut.properties` file (all other details remain the same) and run AUT again with the following command:

```
<AUT_HOME>/AUT/bin> aut execute-fts-post-tasks-921
```

---

**Note** Ensure that the `sourceEqualsdest` parameter is set to true.

---

### Running Averify

Averify performs an integrity check against the Agile database and reports on specific errors. Averify includes a check for missing indexes and inconsistent data stored in the various database tables. Averify only reports errors, and does not attempt to fix them or modify your database.

Running Averify and using the results to eliminate known errors is a prerequisite for diagnosing problems. Averify is not comprehensive, however, and finding zero errors does not certify a database as perfect.

When you download an updated version of AUT, the latest Averify scripts are also included. The latest Averify tool is also available separately on [Oracle Metalink](https://metalink.oracle.com) (see Oracle Metalink -

<https://metalink.oracle.com>). You should run Averify periodically as part of your regular database maintenance procedures.

**To run Averify:**

1. Make sure you have downloaded the latest version of AUT from [Oracle Metalink](https://metalink.oracle.com) (see Oracle Metalink - <https://metalink.oracle.com>).
2. Make sure you have backed up your database.
3. Go to the \$AUT\_HOME\scripts\oracle\utilities\averify directory.
4. Connect to the Agile database from the command line using SQL\*Plus.
5. Run the oracle\_averify9x.sql script.

```
SQL> @oracle_averify9x.sql
```

---

**Note** If errors are generated in the oracle\_averify\_report.log file located in the \$AUT\_HOME\scripts\oracle\utilities\averify directory, contact Agile Support.

---