

# **Oracle® Solaris Cluster Data Service for SWIFTAlliance Access Guide**

SPARC Platform Edition

Copyright © 2000, 2010, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related software documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle America, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. UNIX is a registered trademark licensed through X/Open Company, Ltd.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

# Contents

---

<b>Preface</b> .....	5
<b>1 Installing and Configuring Oracle Solaris Cluster HA for Alliance Access</b> .....	11
Overview of Installing and Configuring HA for Alliance Access .....	11
Oracle Solaris Cluster HA for Alliance Access Overview .....	12
Planning the Oracle Solaris Cluster HA for Alliance Access Installation and Configuration ....	13
Configuration Restrictions .....	13
Configuration Requirements .....	14
Installing and Configuring Alliance Access .....	15
▼ How to Install and Configure Alliance Access .....	15
Verifying the Installation and Configuration of Alliance Access .....	20
▼ How to Verify the Installation and Configuration of Alliance Access .....	20
Installing the HA for Alliance Access Packages .....	20
▼ How to Install the HA for Alliance Access Packages .....	21
Registering and Configuring Oracle Solaris Cluster HA for Alliance Access .....	22
▼ How to Register and Configure Oracle Solaris Cluster HA for Alliance Access as a Failover Service .....	22
Verifying the Oracle Solaris Cluster HA for Alliance Access Installation and Configuration ...	24
▼ How to Verify the Oracle Solaris Cluster HA for Alliance Access Installation and Configuration .....	24
Understanding the Oracle Solaris Cluster HA for Alliance Access Fault Monitor .....	25
Resource Properties .....	25
Probing Algorithm and Functionality .....	25
Debugging Oracle Solaris Cluster HA for Alliance Access .....	26
▼ How to turn on debugging for Oracle Solaris Cluster HA for Alliance Access .....	26
<b>Index</b> .....	29



# Preface

---

*Oracle Solaris Cluster Data Service for SWIFTAlliance Access Guide* explains how to install and configure HA for Alliance Access.

---

**Note** – This Oracle Solaris Cluster release supports systems that use the SPARC and x86 families of processor architectures: UltraSPARC, SPARC64, AMD64, and Intel 64. In this document, x86 refers to the larger family of 64-bit x86 compatible products. Information in this document pertains to all platforms unless otherwise specified.

---

This document is intended for system administrators with extensive knowledge of Oracle software and hardware. Do not use this document as a planning or presales guide. Before reading this document, you should have already determined your system requirements and purchased the appropriate equipment and software.

The instructions in this book assume knowledge of the Oracle Solaris Operating System and expertise with the volume-manager software that is used with Oracle Solaris Cluster software.

## Using UNIX Commands

This document contains information about commands that are specific to installing and configuring Oracle Solaris Cluster data services. The document does *not* contain comprehensive information about basic UNIX commands and procedures, such as shutting down the system, booting the system, and configuring devices. Information about basic UNIX commands and procedures is available from the following sources:

- Online documentation for the Oracle Solaris Operating System
- Oracle Solaris Operating System man pages
- Other software documentation that you received with your system

## Typographic Conventions

The following table describes the typographic conventions that are used in this book.

TABLE P-1 Typographic Conventions

Typeface	Meaning	Example
AaBbCc123	The names of commands, files, and directories, and onscreen computer output	Edit your <code>.login</code> file. Use <code>ls -a</code> to list all files. <code>machine_name% you have mail.</code>
<b>AaBbCc123</b>	What you type, contrasted with onscreen computer output	<code>machine_name% su</code> Password:
<i>aabbcc123</i>	Placeholder: replace with a real name or value	The command to remove a file is <code>rm filename</code> .
<i>AaBbCc123</i>	Book titles, new terms, and terms to be emphasized	Read Chapter 6 in the <i>User's Guide</i> . <i>A cache</i> is a copy that is stored locally. Do <i>not</i> save the file. <b>Note:</b> Some emphasized items appear bold online.

## Shell Prompts in Command Examples

The following table shows the default UNIX system prompt and superuser prompt for shells that are included in the Oracle Solaris OS. Note that the default system prompt that is displayed in command examples varies, depending on the Oracle Solaris release.

TABLE P-2 Shell Prompts

Shell	Prompt
Bash shell, Korn shell, and Bourne shell	\$
Bash shell, Korn shell, and Bourne shell for superuser	#
C shell	machine_name%
C shell for superuser	machine_name#

## Related Documentation

Information about related Oracle Solaris Cluster topics is available in the documentation that is listed in the following table. All Oracle Solaris Cluster documentation is available at <http://docs.sun.com>.

Topic	Documentation
Data service administration	<i>Oracle Solaris Cluster Data Services Planning and Administration Guide</i> Individual data service guides
Concepts	<i>Oracle Solaris Cluster Concepts Guide</i>
Overview	<i>Oracle Solaris Cluster Overview</i>
Software installation	<i>Oracle Solaris Cluster Software Installation Guide</i>
System administration	<i>Oracle Solaris Cluster System Administration Guide</i>
Hardware administration	<i>Oracle Solaris Cluster 3.3 Hardware Administration Manual</i> Individual hardware administration guides
Data service development	<i>Oracle Solaris Cluster Data Services Developer's Guide</i>
Error messages	<i>Oracle Solaris Cluster Error Messages Guide</i>
Command and function reference	<i>Oracle Solaris Cluster Reference Manual</i>

For a complete list of Oracle Solaris Cluster documentation, see the release notes for your release of Oracle Solaris Cluster at <http://docs.sun.com>.

## Related Third-Party Web Site References

Third-party URLs that are referenced in this document provide additional related information.

---

**Note** – Oracle is not responsible for the availability of third-party web sites mentioned in this document. Oracle does not endorse and is not responsible or liable for any content, advertising, products, or other materials that are available on or through such sites or resources. Oracle will not be responsible or liable for any actual or alleged damage or loss caused or alleged to be caused by or in connection with use of or reliance on any such content, goods, or services that are available on or through such sites or resources.

---

## Documentation, Support, and Training

See the following web sites for additional resources:

- Documentation (<http://docs.sun.com>)
- Support (<http://www.oracle.com/us/support/systems/index.html>)
- Training (<http://education.oracle.com>) – Click the Sun link in the left navigation bar.

## Oracle Welcomes Your Comments

Oracle welcomes your comments and suggestions on the quality and usefulness of its documentation. If you find any errors or have any other suggestions for improvement, go to <http://docs.sun.com> and click Feedback. Indicate the title and part number of the documentation along with the chapter, section, and page number, if available. Please let us know if you want a reply.

Oracle Technology Network (<http://www.oracle.com/technetwork/index.html>) offers a range of resources related to Oracle software:

- Discuss technical problems and solutions on the [Discussion Forums](http://forums.oracle.com) (<http://forums.oracle.com>).
- Get hands-on step-by-step tutorials with [Oracle By Example](http://www.oracle.com/technology/obe/start/index.html) (<http://www.oracle.com/technology/obe/start/index.html>).
- Download [Sample Code](http://www.oracle.com/technology/sample_code/index.html) ([http://www.oracle.com/technology/sample\\_code/index.html](http://www.oracle.com/technology/sample_code/index.html)).

## Getting Help

If you have problems installing or using Oracle Solaris Cluster, contact your service provider and provide the following information:

- Your name and email address (if available)
- Your company name, address, and phone number
- The model number and serial number of your systems
- The release number of the Oracle Solaris Operating System (for example, Oracle Solaris 10)
- The release number of Oracle Solaris Cluster (for example, Oracle Solaris Cluster 3.3)

Use the following commands to gather information about each node on your system for your service provider.

Command	Function
<code>prtconf -v</code>	Displays the size of the system memory and reports information about peripheral devices
<code>psrinfo -v</code>	Displays information about processors
<code>showrev -p</code>	Reports which patches are installed
<code>prtdiag -v</code>	Displays system diagnostic information
<code>/usr/cluster/bin/clnode show-rev</code>	Displays Oracle Solaris Cluster release and package version information

Also have available the contents of the `/var/adm/messages` file.



# Installing and Configuring Oracle Solaris Cluster HA for Alliance Access

---

This Chapter explains how to install and configure HA for Alliance Access.

---

**Note** – In the current version, SWIFTAlliance Access is renamed as Alliance Access. You can use the Oracle Solaris Cluster HA for Alliance Access with both the product names.

---

This Chapter contains the following sections.

- “Overview of Installing and Configuring HA for Alliance Access” on page 11
- “Oracle Solaris Cluster HA for Alliance Access Overview” on page 12
- “Planning the Oracle Solaris Cluster HA for Alliance Access Installation and Configuration” on page 13
- “Installing and Configuring Alliance Access” on page 15
- “Verifying the Installation and Configuration of Alliance Access” on page 20
- “Installing the HA for Alliance Access Packages” on page 20
- “Registering and Configuring Oracle Solaris Cluster HA for Alliance Access” on page 22
- “Verifying the Oracle Solaris Cluster HA for Alliance Access Installation and Configuration” on page 24
- “Understanding the Oracle Solaris Cluster HA for Alliance Access Fault Monitor” on page 25
- “Debugging Oracle Solaris Cluster HA for Alliance Access” on page 26

## Overview of Installing and Configuring HA for Alliance Access

Table 1–1 Lists the tasks for installing and configuring Oracle Solaris Cluster HA for Alliance Access. Perform these tasks in the order that they are listed.

TABLE 1-1 Task Map: Installing and Configuring Oracle Solaris Cluster HA for Alliance Access

Task	For Instructions, Go To
1. Plan the installation.	<a href="#">“Planning the Oracle Solaris Cluster HA for Alliance Access Installation and Configuration” on page 13</a>
2. Install Oracle Solaris Cluster HA for Alliance Access Packages.	<a href="#">“How to Install and Configure Alliance Access” on page 15</a>
3. Verify installation and configuration.	<a href="#">“Verifying the Installation and Configuration of Alliance Access” on page 20</a>
4. Register and Configure Oracle Solaris Cluster HA for Alliance Access.	<a href="#">“Registering and Configuring Oracle Solaris Cluster HA for Alliance Access” on page 22</a>
5. Verify Oracle Solaris Cluster HA for Alliance Access Installation and Configuration.	<a href="#">“Verifying the Oracle Solaris Cluster HA for Alliance Access Installation and Configuration” on page 24</a>
6. Understand Oracle Solaris Cluster HA for Alliance Access fault monitor.	<a href="#">“Understanding the Oracle Solaris Cluster HA for Alliance Access Fault Monitor” on page 25</a>
7. Debug Oracle Solaris Cluster HA for Alliance Access.	<a href="#">“Debugging Oracle Solaris Cluster HA for Alliance Access” on page 26</a>

## Oracle Solaris Cluster HA for Alliance Access Overview

The HA agent is written to work with Alliance Access versions 5.5, 5.9, 6.0, 6.2 and 6.3. IBM DCE version 3.2 is not used anymore by Alliance Access 5.9 and later, and must only be installed for Alliance Access 5.5. Alliance Access is a trademark of SWIFT.

The Oracle Solaris Cluster HA for Alliance Access data service provides a mechanism for orderly startup, shutdown, fault monitoring, and automatic failover of the Oracle Solaris Cluster service. The Oracle Solaris Cluster components protected by the Oracle Solaris Cluster HA for Alliance Access data service are the following.

TABLE 1-2 Protection of Components

Component	Protected by
DCE daemon	Oracle Solaris Cluster HA for Alliance Access (version 5.5 only)
Alliance Access	Oracle Solaris Cluster HA for Alliance Access

---

**Note** – By default the HA agent provides a fault monitor for the DCE component only when using the Alliance Access 5.5. The fault monitoring for Alliance Access is switched off by default. If the Alliance Access application fails, the agent will not restart the Alliance Access application automatically. This behavior was explicitly requested by SWIFT. It will enable you to operate the application in a way that the probe does not interfere with the normal behavior of some Alliance Access features like:

- operator manually triggering the Alliance Access restart function , for example, to run Alliance Access in housekeeping mode.
- automatic or scheduled Alliance Access restart, for example, to run database backup and other maintenance or end-of-day processes.
- any graceful Alliance Access restart or recovery, in case of a Alliance Access transient local error.

The HA agent provides the start, stop, takeover, and switchover functionality. This means that when a node fails, the other node will automatically start the Alliance Access application. The HA agent also provides an option to turn on fault monitoring for Alliance Access at registration time. However, this option is not recommended by SWIFT.

---

## Planning the Oracle Solaris Cluster HA for Alliance Access Installation and Configuration

This section contains the information you need to plan your Oracle Solaris Cluster HA for Alliance Access installation and configuration.

### Configuration Restrictions

This section provides a list of software and hardware configuration restrictions that apply to Oracle Solaris Cluster HA for Alliance Access only.




---

**Caution** – Your data service configuration might not be supported if you do not observe these restrictions.

---

- You can configure the Oracle Solaris Cluster HA for Alliance Access *only as a HA agent and not as a scalable agent*.
- You can install the Alliance Access software on a global file system. Best practice is to use a failover file system. For Alliance Access 5.5, you must install the IBM DCE software on local storage.
- Only one Alliance Access instance is supported by this agent.

For restrictions that apply to all data services, see the *Solaris Cluster Release Notes*.

## Configuration Requirements

These requirements apply to Oracle Solaris Cluster HA for Alliance Access only. You must meet these requirements before you proceed with your Oracle Solaris Cluster HA for Alliance Access installation and configuration. Follow the Alliance Access installation guide for the installation of the mandatory patch levels and the installation of the software.



**Caution** – Your data service configuration might not be supported if you do not adhere to these requirements.

### Oracle Solaris Cluster components and their dependencies

Configure the Oracle Solaris Cluster HA for Alliance Access data service to protect a Oracle Solaris Cluster instance and its respective components. These components, and their dependencies, are briefly described next.

Component	Description
DCE daemon	→ <i>SUNW.LogicalHost</i> resource
Alliance Access	→ <i>SUNW.LogicalHost</i> resource → <i>SUNW.HAStoragePlus</i> resource The <i>SUNW.HAStoragePlus</i> resource manages the Alliance Access System Mount points and ensures that Oracle Solaris Cluster is not started until these are mounted. → <i>DCE daemon</i> (version 5.5 only)

The Oracle Solaris Cluster component has two configuration and registration files in the `/opt/SUNWcsaa/util` directory. These files enable you to register the Oracle Solaris Cluster component with Solaris Cluster.

Within these files, the appropriate dependencies have already been defined. You must update the `saa_config` file before you run the `saa_register` script.

# Installing and Configuring Alliance Access

This section describes the procedure to install and configure Alliance Access.

References will be made to some user-accessible directories for Alliance Access throughout the following sections.

---

**Note** – HA for Alliance Access can be configured to run in a whole root or a sparse root non-global zone for Alliance Access version 6.0, 6.2, and 6.3 if required.

---

## ▼ How to Install and Configure Alliance Access

Use this procedure to install and configure Alliance Access.

---

**Note** – IBM DCE client software is a prerequisite for Alliance Access version 5.5. The client software must be installed and configured before the Alliance Access application.

---

### 1 Create the resources for Alliance Access.

- **Create a resource group for Alliance Access.**

```
# clresourcegroup create [-n node-zone-list] swift-rg
```

-n node-zone-list

Specifies a comma-separated, ordered list of zones that can master the resource group.

The format of each entry in the list is node. In this format, node specifies the node name and zone specifies the name of a non-global Solaris zone. To specify the global zone, or to specify a node without non-global zones, specify only node. This list is optional. If you omit this list, the global zone of each cluster node can master the resource group.

- **Create a logical host.**

Add the hostname and IP address in the `/etc/inet/hosts` file on all cluster nodes or zones that can master the resource group. Register the logical host and add it to the resource group.

```
# clreslogicalhostname create -g swift-rg -l swift-lh swift-saa-lh-rs
```

- **Create the device group and file system.**

See *Solaris Cluster Data Services Installation and Configuration Guide* for instructions on how to create global file systems.

- **Create an HAStoragePlus resource.**

It is recommended to create a HAStoragePlus failover resource to contain the Alliance Access application and configuration data instead of using the global file system.

```
# clresource create -g swift-rg \
-t SUNW.HAStoragePlus \
-x FilesystemMountPoints=/global/saadg/alliance swift-ds
```

- **Bring the resource group online.**

```
# clresouregroup online -M swift-rg
```

- **Create the configuration directory.**

This directory contains Alliance Access information and creates a link from the /usr

```
# cd /global/saadg/alliance
# mkdir swa
# ln -s /global/saadg/alliance/swa /usr/swa
```

---

**Note** – For Solaris 10 only: If you install Alliance Access in a sparse root zone, that is if the /usr directory is inherited in read-only mode through a loopback mount, the link needs to be created within the global zone.

---

## 2 Install IBM DCE client software on all cluster nodes or zones that can master the resource group.



**Caution** – This step is valid only for Alliance Access versions prior to 5.9 and should only be installed when needed.

Skip this step if you are using Alliance Access version 5.9 or later.

- **Install IBM DCE client software on all cluster nodes or zones that can master the resource group.** Use local disks to install this application. The software is shipped in Sun package format (IDCEclnt). Because the installed files will reside at various locations on your system, it is not practical to have this installed on global file systems. Install this application on both cluster nodes.

```
# pkgadd -d ./IDCEclnt.pkg
```

- **Configure DCE client RPC.**

```
# /opt/dcelocal/tcl/config.dce -cell_name swift -dce_hostname swift-lh RPC
```

- **Test DCE.**

Run the tests on all cluster nodes or zones that can master the resource group.

```
# /opt/dcelocal/tcl/start.dce
```

Verify that the dced daemon is running.

```
# /opt/dcelocal/tcl/stop.dce
```

## 3 Install Alliance Access software.

Perform the following steps on all cluster nodes or zones that can master the resource group. The steps vary between different versions of Alliance Access. You must perform the steps corresponding to the version of Alliance Access you are using.

- For Alliance Access 6.0 and earlier only: Create the users `all_admin`, `all_usr` and the group `alliance` on all cluster nodes or zones that can master the resource group with the same user ID and group ID.

```
# groupadd -g groupid alliance
# useradd -m -g alliance -d /export/home/all_admin -s /usr/bin/ksh all_admin
# useradd -m -g alliance -d /export/home/all_usr -s /usr/bin/ksh all_usr
```

On Solaris 10: Create a project called `swift` and assign the users `all_admin` and `all_usr` to it.

```
# projadd -U all_admin,all_usr swift
```

- For Alliance Access 6.2 and 6.3: Create the user `all_admin` and the groups `alliance` and `sagsnlg` on all cluster nodes or zones that can master the resource group with the same user ID and group ID. Also, create a project called `swift` and assign the users `all_admin` to it.

```
# groupadd -g groupid alliance
# groupadd -g groupid sagsnlg
# useradd -m -g alliance -G sagsnlg -d /export/home/all_admin -s \
/usr/bin/ksh all_admin
# projadd -U all_admin swift
```

- On Solaris 10: Set the values of the resource controls for the project `swift`.

For Alliance Access 6.0 and earlier versions only:

```
# projmod -s -K "project.max-sem-ids=(privileged,128,deny)" swift
# projmod -s -K "process.max-sem-nsems=(privileged,512,deny)" swift
# projmod -s -K "process.max-sem-ops=(privileged,512,deny)" swift
# projmod -s -K "project.max-shm-memory=(privileged,4294967295,deny)" swift
# projmod -s -K "project.max-shm-ids=(privileged,128,deny)" swift
# projmod -s -K "process.max-msg-qbytes=(privileged,4194304,deny)" swift
# projmod -s -K "project.max-msg-ids=(privileged,500,deny)" swift
# projmod -s -K "process.max-sem-messages=(privileged,8192,deny)" swift
```

For Alliance Access 6.2 and 6.3 only:

```
# projmod -s -K "project.max-sem-ids=(privileged,1320,deny)" swift
# projmod -s -K "project.max-shm-ids=(privileged,1500,deny)" swift
# projmod -s -K "project.max-shm-memory=(privileged,4294967295,deny)" swift
# projmod -s -K "project.max-msg-ids=(privileged,800,deny)" swift
# projmod -s -K "process.max-sem-nsems=(privileged,512,deny)" swift
# projmod -s -K "process.max-sem-ops=(privileged,512,deny)" swift
# projmod -s -K "process.max-msg-qbytes=(privileged,10485760,deny)" swift
# projmod -s -K "process.max-msg-messages=(privileged,8192,deny)" swift
# projmod -s -K "process.max-stack-size=(basic,33554432,deny)" swift
```

```
# projmod -s -K "process.max-data-size=(basic,8.0EB,deny)" swift
# projmod -s -K "process.max-file-descriptor=(basic,1000,deny)" swift
```

The previous values are examples. For more accurate values, refer to the latest SWIFT documentation release notes of the corresponding version.

- On Solaris 10:

For Alliance Access 6.0 and earlier versions only:

Assign the project `swift` as the default project for `all_admin` and `all_usr` by editing the file `/etc/user_attr` and typing the following two lines at the end of the file.

```
all_admin:::project=swift
all_usr:::project=swift
```

For Alliance Access 6.2 and 6.3 only:

Assign the project `swift` as the default project for `all_admin` by editing the file `/etc/user_attr` and typing the following line at the end of the file.

```
all_admin:::project=swift
```

- For versions prior to Solaris 10, refer to the latest SWIFT documentation and release notes to determine the necessary setup for `/etc/system`.

Use the shared storage configured in [Step 1](#) for the installation of this application. The installation procedure will modify system files and might reboot the system. After rebooting, you must continue with the installation on the same node or zone. Ensure that the resource group is online on this node or zone.

For Alliance Access 6.0 and earlier versions only:

Repeat the installation of the software on the other node or zone that can master the resource group, but you must end the installation before the Alliance Access software licensing step.

#### 4 For Alliance Access 6.0 and earlier versions only: Continue configuring Alliance Access application.

To enable clients to connect to the failover IP address, create a file named `.alliance_ip_name` (`interfaces.rpc` in versions 5.9 and 6.0) on the data subdirectory of the Alliance Access software.

If you are using the same file system as shown in the examples, this directory will be `/global/saadg/alliance/data`. This file must contain the IP address of the logical host as configured within the Alliance Access resource group.

```
# cd /global/saadg/alliance/data
# chown all_admin:alliance interfaces.rpc
```

If Alliance Messenger is licensed, create a file called `interfaces.mas` and add the cluster logical IP address used to communicate with SAM.

```
# cd /global/saadg/alliance/data
# chown all_admin:alliance interfaces.mas
```

## 5 Add a symbolic link and entries.

- Add the symbolic link `/usr/swa` on all cluster nodes or zones that can master the resource group, see Step 1 last bullet.
- Entries in `/etc/services` have to be added on all cluster nodes or zones that can master the resource group. This can be done as root by running the `/usr/swa/apply_alliance_ports` script.

- For Alliance Access 6.0 and earlier versions only:

The `rc.alliance` and `rc.swa_boot` scripts (`swa_rpcd` in Alliance Access versions prior to 5.9) in `/etc/init.d` must remain in place. Any references to these files in `/etc/rc?.d` need to be removed and the access rights must be as follows:

```
# cd /etc/init.d
# chmod 750 rc.alliance rc.swa_boot
# chown root:sys rc.alliance rc.swa_boot
```

If the Alliance Access Installer displays “Start this SWIFT Alliance at Boottime”, choose **No**.

You must copy the `rc.alliance` and `rc.swa_boot` scripts to all other cluster nodes or zones that can master the resource group:

```
# scp rc.alliance rc.swa_boot node2:/etc/init.d
```

---

**Note** – You must not configure to automatically start at boot time through the `saa_configbootstrap` command for Alliance Access 6.2 and 6.3.

---

## 6 Install Alliance Access Remote API (RA).

- Install RA after Alliance Access on shared storage using the following options:

Instance RA1 (default), user `all_admin`

- Alliance Access 6.0 and earlier versions only:

Copy the files in the home directory of the `all_admin` and `all_usr` user to all cluster nodes or zones that can master the resource group.

- Alliance Access 6.2 and 6.3 only:

Copy the files in the home directory of the `all_admin` user to all cluster nodes or zones that can master the resource group. Copy the `root/InstallShield` directory to all cluster nodes or zones that can master the resource group.

## Verifying the Installation and Configuration of Alliance Access

This section contains the procedure you need to verify the installation and configuration.

### ▼ How to Verify the Installation and Configuration of Alliance Access

This procedure does not verify that your application is highly available because you have not yet installed your data service.

#### 1 Start the Alliance Access application.

For Alliance Access versions other than Alliance Access version 5.5, type:

```
# su - all_admin
```

For Alliance Access version 5.5, choose Alliance —> Start SWIFTAlliance Servers.

---

**Note** – If DCE does not start, choose GUI: OS Configuration —> DCE RPC.

---

#### 2 Test the application.

a. Start the Alliance Access application.

b. Choose Alliance —> Start User Interface.

#### 3 Stop the Alliance Access application.

a. Start the GUI.

```
# su - all_admin
```

b. Choose Alliance —> Stop SWIFTAlliance Servers.

## Installing the HA for Alliance Access Packages

If you did not install the HA for Alliance Access packages during your initial Oracle Solaris Cluster installation, perform this procedure to install the packages. To install the packages, use the `installer` program.

---

**Note** – You need to install the HA for Alliance Access packages in the global cluster and not in the zone cluster.

---

## ▼ How to Install the HA for Alliance Access Packages

Perform this procedure on each cluster node where you are installing the HA for Alliance Access packages.

You can run the `installer` program with a command-line interface (CLI) or with a graphical user interface (GUI). The content and sequence of instructions in the CLI and the GUI are similar.

---

**Note** – Even if you plan to configure this data service to run in non-global zones, install the packages for this data service in the global zone. The packages are propagated to any existing non-global zones and to any non-global zones that are created after you install the packages.

---

**Before You Begin** Ensure that you have the Oracle Solaris Cluster installation media.

If you intend to run the `installer` program with a GUI, ensure that your `DISPLAY` environment variable is set.

**1 On the cluster node where you are installing the data service packages, become superuser.**

**2 Load the Oracle Solaris Cluster installation media into the DVD-ROM drive.**

If the Volume Management daemon `vold(1M)` is running and configured to manage DVD-ROM devices, the daemon automatically mounts the DVD-ROM on the `/cdrom` directory.

**3 Change to the installation wizard directory of the DVD-ROM.**

- If you are installing the data service packages on the SPARC platform, type the following command:

```
# cd /cdrom/cdrom0/Solaris_sparc
```

- If you are installing the data service packages on the x86 platform, type the following command:

```
# cd /cdrom/cdrom0/Solaris_x86
```

**4 Start the installation wizard.**

```
# ./installer
```

**5 When you are prompted, accept the license agreement.**

**6 From the list of Oracle Solaris Cluster agents under Availability Services, select the data service for Alliance Access.**

- 7 If you require support for languages other than English, select the option to install multilingual packages.**  
English language support is always installed.
- 8 When prompted whether to configure the data service now or later, choose Configure Later.**  
Choose Configure Later to perform the configuration after the installation.
- 9 Follow the instructions on the screen to install the data service packages on the node.**  
The installation wizard displays the status of the installation. When the installation is complete, the wizard displays an installation summary and the installation logs.
- 10 (GUI only) If you do not want to register the product and receive product updates, deselect the Product Registration option.**  
The Product Registration option is not available with the CLI. If you are running the installation wizard with the CLI, omit this step.
- 11 Exit the installation wizard.**
- 12 Unload the installation media from the DVD-ROM drive.**
  - a. To ensure that the DVD-ROM is not being used, change to a directory that does *not* reside on the DVD-ROM.**
  - b. Eject the DVD-ROM.**  

```
# eject cdrom
```

**Next Steps** Go to [“Registering and Configuring Oracle Solaris Cluster HA for Alliance Access”](#) on page 22

## Registering and Configuring Oracle Solaris Cluster HA for Alliance Access

This section contains the procedures you need to configure Oracle Solaris Cluster HA for Alliance Access.

### ▼ How to Register and Configure Oracle Solaris Cluster HA for Alliance Access as a Failover Service

This procedure assumes that you installed the data service packages during your initial Solaris Cluster installation.

Steps 1 to 6 will normally already be done in order to prepare for the installation of the IBM DCE and Alliance Access software. See “[How to Install and Configure Alliance Access](#)” on [page 15](#). Typically, you should go directly to step 7.

**1 Become superuser on one of the nodes in the cluster that will host Oracle Solaris Cluster.**

**2 Register the SUNW.gds resource type.**

```
# clresourcetype register SUNW.gds
```

**3 Register the SUNW.HAStoragePlus resource type.**

```
# clresourcetype register SUNW.HAStoragePlus
```

**4 Create a failover resource group.**

```
# clresourcegroup create [-n node-zone-list] swift-rg
```

`-n node-zone-list` Specifies a comma-separated, ordered list of zones that can master the resource group. The format of each entry in the list is `node`. In this format, `node` specifies the node name and `zone` specifies the name of a non-global Solaris zone. To specify the global zone, or to specify a node without non-global zones, specify only `node`. This list is optional. If you omit this list, the global zone of each cluster node can master the resource group.

**5 Create a resource for the Oracle Solaris Cluster Disk Storage.**

```
# clresource create -g swift-rg \  
-t SUNW.HAStoragePlus \  
-x FilesystemMountPoints=/global/saadg/alliance swift-ds
```

**6 Create a resource for the Oracle Solaris Cluster Logical Hostname.**

```
# clreslogicalhostname create -g swift-rg\  
-h swift-lh swift-lh-rs
```

**7 Enable the failover resource group that now includes the Oracle Solaris Cluster Disk Storage and Logical Hostname resources.**

```
# clresourcegroup online -M swift-rg
```

**8 Create a resource for Alliance Access.**

**a. Before running this script, check that the names of the resources match what is configured in `/opt/SUNWscsaa/util/saa_config`.**

```
# /opt/SUNWscsaa/util/saa_register
```

**b. Run the registration script provided as part of the Alliance Access HA agent.**

**9 Start the Alliance Access instance manually.**

```
su - all_admin
```

The GUI will open up. From within the GUI, select the menu Alliance - Start Alliance Servers

**10 Stop the Alliance Access manually.**

```
su - all_admin
```

The GUI will come up. Stop the application from within the GUI.

**11 Enable each Oracle Solaris Cluster resource.**

```
# clresource status -g swift-rg
# clresource enable swift-saa-rs
```

## Verifying the Oracle Solaris Cluster HA for Alliance Access Installation and Configuration

This section describes the procedure to verify that you have installed and configured your data service correctly.

### ▼ How to Verify the Oracle Solaris Cluster HA for Alliance Access Installation and Configuration

**1 Become superuser on one of the nodes in the cluster that will host Oracle Solaris Cluster.****2 Ensure all the Oracle Solaris Cluster resources are online with `cluster status`.**

```
# cluster status
```

For each Oracle Solaris Cluster resource that is not online, use the `clresource` command as follows.

```
# clresource enable resource-name
```

**3 Run the `clresourcegroup` command to switch the Oracle Solaris Cluster resource group to another cluster node, such as `node2`.**

```
# clresourcegroup switch swift-rg -h node2
```

**4 Check that Alliance Access is stopped on the first node and that the application is restarted on the second node.**

When using a failover file system, this should disappear on the first node and will be mounted on the second node.

# Understanding the Oracle Solaris Cluster HA for Alliance Access Fault Monitor

This section describes the Oracle Solaris Cluster HA for Alliance Access fault monitor's probing algorithm or functionality, and states the conditions, messages, and recovery actions associated with unsuccessful probing.

For conceptual information on fault monitors, see the *Solaris Cluster Concepts Guide*.

## Resource Properties

The Oracle Solaris Cluster HA for Alliance Access fault monitor uses the same resource properties as resource type `SUNW.gds`, refer to the `SUNW.gds(5)` man page for a complete list of resource properties used.

## Probing Algorithm and Functionality

By default, the HA agent provides a fault monitor for the DCE component only when using Alliance Access 5.5. The fault monitoring for Alliance Access is switched off by default. If the Alliance Access application fails, the agent will not restart the Alliance Access application automatically. This behavior was explicitly requested by SWIFT. It will enable you to operate the application in a way that the probe does not interfere with the normal behavior of some Alliance Access features like:

- operator manually triggering the Alliance Access restart function, for example, to run Alliance Access in housekeeping mode.
- automatic or scheduled Alliance Access restart, for example, to run database backup and other maintenance or end-of-day processes.
- any graceful Alliance Access restart or recovery, in case of a Alliance Access transient local error.

The HA agent will update the resource status message to output `Degraded - SAA Instance offline`.

If an automatic failover occurs with default setting, it is most likely that there was a DCE problem. The Alliance Access application will cause a failover only when it does not start on the current node.

The HA agent provides an option to turn on fault monitoring for Alliance Access at registration time. However, this option is not recommended by SWIFT. The optional probing checks for the existence of the Alliance Access instance by calling the `alliance` command that is part of the

application and by evaluating its return code. If the Alliance Access instance is not running, return code 100 is sent to `SUNW.gds`, which in turn will perform an automatic restart depending on the configuration of the resource properties.

## Debugging Oracle Solaris Cluster HA for Alliance Access

### ▼ How to turn on debugging for Oracle Solaris Cluster HA for Alliance Access

Each Oracle Solaris Cluster component has a `DEBUG` file in `/opt/SUNWscsa/etc` directory, where `saa` is a three-character abbreviation for the respective Oracle Solaris Cluster component.

These files enable you to turn on debugging for all Oracle Solaris Cluster instances or for a specific Oracle Solaris Cluster instance on a particular node with Oracle Solaris Cluster. If you require debugging to be turned on for Oracle Solaris Cluster HA for Alliance Access across the entire Oracle Solaris Cluster installation, repeat this step on all nodes or zones that can master the resource group.

#### 1 Edit the `/etc/syslog.conf` file.

Change `daemon.notice` to `daemon.debug`.

```
# grep daemon /etc/syslog.conf
*.err;kern.debug;daemon.notice;mail.crit      /var/adm/messages
*.alert;kern.err;daemon.err                  operator
#
```

Change the `daemon.notice` to `daemon.debug` and restart `syslogd`. The following output, from the command `grep daemon /etc/syslog.conf`, shows that `daemon.debug` has been set.

```
# grep daemon /etc/syslog.conf
*.err;kern.debug;daemon.debug;mail.crit      /var/adm/messages
*.alert;kern.err;daemon.err                  operator
#
# pkill -1 syslogd
#
```

#### 2 Edit the `/opt/SUNWscsa/etc/config` file.

Change `DEBUG=` to `DEBUG=ALL` or `DEBUG=resource`

```
# cat /opt/SUNWscsa/etc/config
#
# Copyright 2003 Sun Microsystems, Inc. All rights reserved.
# Use is subject to license terms.
#
# Usage:
```

```
#      DEBUG=<RESOURCE_NAME> or ALL  
#  
DEBUG=ALL  
#
```

---

**Note** – To turn off debugging, reverse the previous steps.

---



# Index

---

## C

clnode command, 9

commands

clresource, 24

clresourcegroup, 23

clresourcetype, 23

cluster status, 24

node information, 8

Configuration

Alliance Access, 15–19

directory for SAA, 16

Registering Solaris Cluster HA for Alliance

Access, 22–24

Requirements, 14

Restrictions, 13–14

Verify, 20

Configure, DCE, 16

## D

Debugging, How to turn on, 26–27

## F

Fault Monitor

Probing Algorithm and Functionality in, 25–26

Resource Properties, 25

Understanding, 25–26

## G

global zone, 21

## H

HA for Alliance Access

installing, 20–22

software packages, installing, 20–22

help, 8–9

## I

Install

Alliance Access, 15–19

DCE, 16

installing, HA for Alliance Access, 20–22

## L

local zones, *See* non-global zones

## M

messages file, 9

## N

non-global zones, 21

## **P**

packages, 20–22  
prtconf -v command, 9  
prtdiag -v command, 9  
psrinfo -v command, 9

## **R**

Resource  
    Alliance Access, 23  
    logical host, 23  
    SUNW.HAStoragePlus, 23  
Resource Group, 15, 23  
    logical host, 15  
Resource Types  
    SUNW.gds, 23  
    SUNW.HAStoragePlus, 23  
restrictions, zones, 21

## **S**

show - rev subcommand, 9  
showrev -p command, 9  
software packages, 20–22

## **T**

technical support, 8–9  
Test, DCE, 16

## **V**

/var/adm/messages file, 9

## **Z**

zones, 21