

Oracle® Enterprise Manager Ops Center

Creating Oracle Solaris 10 Zones Guide

12c Release 1 (12.1.0.0.0)

E27335-01

April 2012

This guide provides an end-to-end example for how to use Oracle Enterprise Manager Ops Center.

Overview

This example shows you how to create a non-global zone on an Oracle Solaris 10 operating system. The non-global zone type is a whole root zone. The non-global zone configuration details are: shared IP zone, local storage and file system.

A whole root non-global zone uses a root file system that does not share components of the global zone's root file system. You can define the size of the root file system for the non-global zone. The default size for the root file system is eight (8) GBytes for whole root zones.

Profile and plan templates guide you through the steps needed to create a customized discovery profile and create zones plan for your organization. Your customized profiles and plans are saved in the Plan Management section. You can use and reuse the plans to manage assets and to create zones.

See [Related Articles and Resources](#) for links to related information and articles about different zone configurations, including choosing the type of storage library, complex network configurations, and server pools that enable you to migrate zones between pools.

What You Need

Before creating zones, you must determine where to store the zone's metadata. Metadata includes the configuration of the zone's operating system, CPU, memory, and network. The storage library must have sufficient space to accommodate the metadata.

You can use the local filesystem on the virtual host's server, an NFS server, or a SAN network for the zone storage library. The metadata is stored on either a local filesystem or an NFS server. When you create a guest, you assign it to one of the storage libraries associated with its virtual host. The guest's data, which results from its operations, can reside in the same storage library or in a different storage library.

You need the following to create an Oracle Solaris 10 zone:

1. Discover and manage an Oracle Solaris 10 OS.
2. Prepare a global zone.
 - Zone storage. For local storage, nothing is required. The filesystem is always implemented as a ZFS filesystem.

- Network. You will need a network that is associated with the global zone and that is available for the zone. This example uses the default network that is created when you add the OS.
 - IP address for the zone. When you use Shared IP mode, the global zone is sharing its IP link with the zone.
3. A password or SSH key to log into the zone. This example uses a user name and password.
 4. Appropriate roles and permissions. You need the following Oracle Enterprise Manager Ops Center roles:
 - Asset admin – Discover and manage virtualization hosts.
 - Profile and plan admin – Create and manage zone profiles and plans.
 - Virtualization admin – Create and manage zones.

Hardware and Software Configuration

In this example, you are creating a zone that has a shared IP mode network configuration. The storage library is the local filesystem. Each zone has a default local filesystem storage library named `/guests` where data and metadata for the host's guests are stored.

Configure the following:

- Install Oracle Solaris 10 operating system. This example uses Oracle Solaris 10 10/09.
- At least 5 GB File system and at least 6 GB virtual disk for Zone storage.
- Local storage for the zone metadata. This example uses the local library.

Creating an Oracle Solaris 10 Zone


The following tasks in this example:

1. [Add an OS to the User Interface](#)
2. [Create an Oracle Solaris 10 Whole Root Zone Profile and Plan](#)
3. [Apply the Plan to Create a New Zone](#)

Add an OS to the User Interface

Use a Discovery profile to add an asset to the Oracle Enterprise Manager Ops Center UI. The following task shows you how to create and run a new Discovery profile to add an Oracle Solaris 10 OS to the UI.


1. In Plan Management, scroll down to Profiles and Policies, then click Discovery.



2. Click Create Profile in the Actions pane.
3. Enter a name for the discovery profile, and select Solaris/Linux OS as the type of asset to be discovered. Click Next.



4. Click Next to skip adding tags.
5. Do not specify IP addresses at this time. Click Next.
6. Define the discovery credentials and management option.
 - To use previously defined credentials, click Select and choose from the list
 - To create a new set of credentials, click New to launch a pop-up wizard.



- a. For new credentials, enter a name and description that identifies the credential. Enter the root user name and password for the system, then click OK to return to the Discovery Credentials page.

Create Profile - Discover Create Credentials ? **ORACLE**

Steps **Help**

1. Identify Profile
2. Tags
3. IP Ranges
4. **Discovery Credentials**
5. Summary

*** Indicates Required Field**

*** Name:** S10 Credentials

Description: Oracle Solaris 10 credentials

SSH

*** Login User:** user name

*** Password:** ●●●●●●

*** Confirm Password:** ●●●●●●

Privileged Role:

Role Password:

Confirm Password:

*** SSH Port:** 22

New Select

- b. In the Management section of the Discovery Credentials page, select Deploy Agent Controller to install Agent Controller on the asset.

Discovery Credentials

Optionally specify the discovery and/or management credential sets for each protocol. These credentials are used to probe the assets. Select an existing set of credentials or create a new set of credentials. [clear](#)

Discovery

SSH: Solaris Credentials New Select

Management

After discovery, an asset must be managed for full data to be reported and actions to be available. Specify whether to manage the assets using Agent Deployment or Agentless.

Deploy Agent Controller. Required for software update and virtualization support.

Manage without Agent Controller. A Proxy Controller periodically probes the asset using SSH.

7. Click Finish to create the Discovery profile. The new profile appears in the center pane.

Discovery Profiles

Discovery Profiles (5)

Name	Description	Subtype
Add Solaris OS		Solaris, Linux OS
GECovmMgrProf		OVM Manager
gzDiscoveryProf		Solaris, Linux OS

8. Double-click the new Discovery profile, then click Add Assets in the Action pane.
9. Enter the host name or IP address, then click Add Now.
A job is launched to discover and manage the asset.


Create an Oracle Solaris 10 Whole Root Zone Profile and Plan

A zone profile defines the zone configuration details and creates a deployment plan that you can use to deploy the profile to create a zone. You can reuse the plan to create additional identical zones, or you can use it to create new plans. You can edit the zone configuration details at any time.

1. In Plan Management, select Oracle Solaris Zone from the Profiles and Policies section.



2. Click Create Profile in the Actions pane.
3. Enter a name and description for the profile, then select Oracle Solaris 10 from the Subtype list.

A screenshot of a dialog box titled "Identify Profile". It contains several fields and options: a required "Name" field with the text "Create Solaris 10 Zone"; a "Description" field with the text "Use this profile and plan to create Oracle Solaris 10 zones with the default network and local library."; a checked checkbox labeled "Create a deployment plan for this profile."; and a "Subtype" dropdown menu with the following options: Subtype, Solaris 10 (which is selected and highlighted), Solaris 11, Solaris 8, and Solaris 9.

4. To identify the zones that are created with this profile, add a zone prefix name and a number to start the series. Do not add any tags for the zone.

Each zone created uses the prefix name appended with a sequential number. For example, if the prefix name is Myzone and the number to start from is 1, the zone names are Myzone1, Myzone2, and Myzone3.

Specify Zone Identity * Indicates Required

Enter the identification for the zones.

* **Zone Name:** Automatic naming; Prefix:
 Starting Number:

Zone Description:

Tags: + x Search

Tag Name	Value

5. Select Native, Whole Root Zone, then click Next.

Specify Zone Installation Source

Select the type of zone:

Native, Whole Root Zone
 Native, Sparse Root Zone
 Branded Zone

Architecture: SPARC x86

Branded Zone Image:

Host ID Prefix:

Starting Number:

Machine Type:

6. Select the Shared CPU model and define one CPU share. Set the memory thresholds and verify that the locked memory threshold value is less than or equal to the physical memory threshold.

Specify Zone Configuration * Indicates Required Field

Select the CPU usage type and memory caps for the new zone.
 See Help for information about how CPU and memory are shared.

CPU Model: Shared Dedicated

* **CPU Shares:**

CPU Cap: Not Capped Capped at:

Physical Memory Cap: Not Capped Capped at:

Locked Memory Cap: Not Capped Capped at:

Virtual Memory Cap: Not Capped Capped at:

You can enable automatic recovery of the zone. Select a value between 0-100 for priority of recovery of the zone.

Automatic Recovery:

Priority of Recovery: 0 100

- The zone uses the default root file system, which is the zone path. Do not define additional file systems. Click Next.

Specify Zone File Systems

The zone will be created with a default root file system which defines the zone path. Click the  icon to add file systems to the zone.

Note - The root file system mount point cannot be modified.

File Systems

File System	Managed Storage	Mount Point	Reserved (GB)	Quota (GB)	Access
/	<input checked="" type="checkbox"/>		8.00	8.00	Read/Write

- In this example the zone uses the local library. Edit the required disk size, as needed. Click Next.

Specify Zone Storage

Select the library and specify the virtual disks that will make up for the zone's storage. The virtual disks are bound to the actual storage during the execution of the profile.

Storage for the metadata Library:

Storage Disks

Library Type	Library Name	Virtual Disk Name	Volume Group	Required Size(GB)
<input type="text" value="Local"/>	file:///guests	vdisk0		9

- Add the network that you want to connect to the zone and the number of connections. The network is not bound until you execute the plan.

Specify Zone Networks

Select one or more networks to connect to the zone. For each selected network, enter the number of connections. The actual binding of the network occurs during profile execution.

Networks

Network Domain	Network Name	Number of Connections
default	10.166.88.0/24	1

- Define the language, time zone, terminal-type, and root password for the zone.
 - Accept the default value, `dynamic`, for the NFSv4 Domain Name.
 - Provide the root password.

- Set the boot properties for the new zone. You can set the zone to boot after it is created or whenever the global zone boots.
- Select the option to deploy the agent for management.

Specify Zone Setup * Indicates Required

Specify language, time zone, terminal type and root password for the zone.

Language: English (7-bit ASCII)

Time Zone: GMT

Terminal Type: X Terminal Emulator

*** NFSv4 Domain Name:** dynamic

*** Root Password:** ●●●●●●

*** Confirm Password:** ●●●●●●

SSH Key:

Boot Variables:

- Automatically boot zone when the global zone is booted
- Automatically boot zone after creation

Management

- Deploy agent for management. Required for software update support.
- Agent-less management. Global Zone will periodically probe the asset via zlogin

11. Click Next to skip the Zone Naming Service.

Specify Zone Naming Services * Indicates Required

Specify the name service, domain name and the corresponding name server for the zone.

Name Service: NONE DNS NIS NIS+ LDAP

12. Click Finish to create the zone profile and associated deployment plan.

The zone profile and the corresponding deployment plan are created and appear in the list of Oracle Solaris Zone Profiles and Oracle Solaris Zone Plans.

Target Type: Solaris Global Zone **Version:** 2
Template Name: Create Oracle Solaris Zones **Release Date:** 03/31/2012 12:16:07 am MDT
Description: Creates Oracle Solaris Zones

Deployment Template Composition

Step	Required Input	Required Profile/Plan
Create Oracle Solaris Zones	profile	Oracle Solaris Zone Profile

Deployment Plans From Template (3)

✎ 📄 📄 📄 ✖ 🔍 Search

Plan Name	Version	Target Type	Description	Failure Policy	Last Modified
Oracle Solaris 10 Zone-plan	1	Global Zone	Created from profi	Stop at failure	03/31/2012 12:15:53

Apply the Plan to Create a New Zone

Use the plan that you created in [Create an Oracle Solaris 10 Whole Root Zone Profile and Plan](#) to create a zone, and then view the new zone in the UI.

1. In Plan Management, expand Deployment plans, then select the Oracle Solaris Zone plan that you created in the previous section.

Navigation

- Message Center
- Assets
- Plan Management
 - Deployment Plans
 - Configure M-Series Hardware, C
 - Configure RAID
 - Configure Server Hardware and
 - Configure Service Processor
 - Configure and Install Dynamic Sy
 - Configure and Install Logical Dorr
 - Configure and Install Oracle Sola
 - Configure and Install Virtual Maci
 - Create Boot Environment
 - Create Dynamic System Domain
 - Create Logical Domains
 - Create Oracle Solaris Zones
 - Oracle Solaris 10 Zone-plan**
 - auto-ZoneProfile1-plan

Oracle Solaris 10 Zone-plan


Details Results Referrers Version History Jobs

Plan Name: Oracle Solaris 10 Zone-plan **Created:** 03/08/2012 12:15:53
Version: 1 **Last Modified:** 03/08/2012 12:15:53
Description: Created from profile **Template:** Create Oracle Solaris Zones
Target Type: Global Zone **Referrers:** 0
Failure Policy: Stop at failure


Deployment Plan Steps

Step	Associated Profile/Deployment Plan	Guests to Create
Create Oracle Solaris Zones	Oracle Solaris 10 Zone v1	1


1. Click Apply Deployment Plan.



2. Select the target from the list of Available Items, then click Add to Target List.



3. Specify the Zone Identity. The fields are populated with the information from the profile.



4. Select local storage as the library to save the zone metadata. Click Next.

Specify Zone Storage

Select the library and specify the virtual disks that will make up for the zone's storage.

Target: ocbm-ipgs14

Storage for the metadata Library: Local file:///guests

Virtual Disk/Storage Specification for Zone Myzone1

Library Type	Library Name	Virtual Disk Name	Volume Group	Required Size(GB)
Local	file:///guests	Myzone1-vdisk0		9

5. Select the shared zone IP stack. In Networks, select a network and IP range, then click Next.

Specify Zone Networks

Specify the IP stack type and IP address range for the zones.

Zone IP Stack: Exclusive Shared

Networks

Networks	Number of Connections	Address Allocation Method	IP Range
192.168.18.0/24@xvm-x4	1	Use Static IP	192.168.18.

6. The Network Resource Assignments page shows the shared network and IP address.
 - Host name – You can change the zone's host name to be different from the zone name, which might be useful when you are using a naming server.
 - Network Connections – You can add, modify, or delete network connections. For example, you can have Network1 and Network2. When you create two zones you can connect Myzone1 to Network1 and Network 2 and connect Myzone2 to Network1 and remove Network2.
 - IP address – The IP address for a set of zones appears in a range. You can enter the IP addresses in a comma delimited list.

Network Resource Assignments

Specify the NICs and the individual IPs.

Target: ocbm-ippgs14

Host Name

Networks for Zone Myzone1

Networks	VLAN ID	NIC	Address Allocation Method	IP Address
10.79.206.0/24@ocbrm-	-	nge0	Use Static IP	10.79.206.1

7. Schedule when you want the job to run.

Schedule Job

Select when the job should be scheduled to execute the deployment plan on the selected targets.

Now

At a later date/time

8. Click Apply to run the job. When the job finishes successfully, the new zone appears in the Asset tree. Click the asset to see the dashboard.

What's Next?

After creating a zone, you can perform various operations, such as boot, reboot, shut down, and halt on the zone. You can use the plan to create additional zones. The Analytics feature enables you to manage zone performance. You can view the CPU and memory utilization for each zone, and an historical view of the top consumers.

Related Articles and Resources

See the *Oracle Enterprise Manager Ops Center Feature Reference Guide* for more information on the features. The documentation is available at <http://www.oracle.com/pls/topic/lookup?ctx=oc121>.

See the Oracle Solaris Zones documentation at <http://www.oracle.com/technetwork/documentation/solaris-10-192992.html> for more information about zones.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Oracle Enterprise Manager Ops Center Creating Oracle Solaris 10 Zones Guide, 12c Release 1 (12.1.0.0.0)
E27335-01

Copyright © 2007, 2012, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle America, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

