

Oracle® Enterprise Manager

System Monitoring Plug-in Installation Guide for IBM DB2 Database

Release 12 (3.4.1.1.0), Release 9 (3.4.1.0.0), and Release 8 (3.3.1.0.0)

E12777-04

November 2010

This document provides a brief description about the Oracle System Monitoring Plug-In for IBM DB2 Database, details on the versions the plug-in supports, prerequisites for installing the plug-in, and step-by-step instructions on how to download, install, verify, and validate the plug-in.

Description

The System Monitoring Plug-in for IBM DB2 Database extends Oracle Enterprise Manager Grid Control to add support for managing IBM DB2 UDB (LUW) database instances. By deploying the plug-in in your Grid Control environment, you gain the following management features:

- Monitor DB2 Database instances.
- Gather configuration data and track configuration changes for DB2 database instances.
- Raise alerts and violations based on thresholds set on monitored targets and configuration data.
- Provide rich out-of-box reports based on the gathered data.
- Support monitoring by a remote Agent. Local Agent is an agent running on the same host as the DB2 database. Remote Agent is an agent running on a host that is different from the host where DB2 database is running.

Platforms Supported

The plug-in supports monitoring of IBM DB2 UDB (LUW) on all the platforms where IBM DB2 UDB can be installed.

Versions Supported

This plug-in supports the following versions of products:

- Enterprise Manager 11g Grid Control Release 1 (11.1.0.1) or higher, or Enterprise Manager 10g Grid Control Release 2 (10.2.0.1) or higher (*Oracle Management Service and Oracle Management Agent*)
- Single-partition IBM DB2 Universal Database (UDB) for Linux, UNIX, and Windows (LUW) Version 8.2 FixPak 2 and above (8.2.x ,9.x.x)

Prerequisites

The following prerequisites must be met before you can use the plug-in:

- Install the following:
 - Enterprise Manager 11g Grid Control Release 1 (11.1.0.1) or higher, or Enterprise Manager 10g Grid Control Release 2 (10.2.0.1) or higher (*Oracle Management Service and Oracle Management Agent*)
 - IBM DB2 Universal JDBC Type 4 driver for IBM DB2 Database (see [Setting Up the JDBC Driver](#))
 - IBM DB2 Universal Database
 - Set and validate the preferred credentials on all Agents where you want to deploy the plug-in. For more information, see [Configure the Management Agent to Deploy the Plug-In](#).
 - Create a suitable operating system user to access the table functions used in IBM DB2. For information about creating a user, see [Using a Suitable Operating System User and Assigning Authorities and Privileges](#).
 - (For Agent running on Microsoft Windows) The OS privileges for the user (set in the Preferred Credentials for the Agent) must meet the requirements documented in the "Setting Credentials for the Job System to Work with Enterprise Manager" section of the *Oracle Database Installation Guide for Microsoft Windows* available at the following locations:
 - **Oracle Database 11g Release 2 (11.2)**
http://www.oracle.com/pls/db112/portal.portal_db?selected=11&frame=#microsoft_windows_installation_guides
 - **Oracle Database 11g Release 1 (11.1)**
http://www.oracle.com/pls/db111/portal.portal_db?selected=11&frame=#microsoft_windows_installation_guides
 - **Oracle Database 10g Release 2 (10.2)**
<http://www.oracle.com/pls/db102/homepage>
-
- Note:** If you do not assign the correct privileges for users, the deployment will fail.
-
- To avoid metric collection errors for *Database Monitoring* metrics, create the table `STMG_DBSIZE_INFO`. For more information, see [Configurations Required for Avoiding Metric Collection Errors for Database Monitoring Metrics](#).
 - If you want to generate alerts using the IBM DB2 Diagnostic Log file (`db2diag.log`), then do the following:
 - Define your match patterns in the `Diag_log_file_match_pattern_file.txt` file that is present in `$ORACLE_HOME/sysman/admin/scripts/emx/ibm_db2_database/`.

- Defined your ignore patterns in the `Diag_log_file_no_match_pattern_file.txt` file that is present in `$ORACLE_HOME/sysman/admin/scripts/emx/ibm_db2_database/`.
- Set the `DIAG_PATH` configuration parameter of the database manager (instance) to correspond to the monitored IBM DB2 database.

Based on the patterns defined in the two files, the System Monitoring Plug-in for IBM DB2 parses the Diagnostic Log file and generates alerts for the satisfied conditions. First, the plug-in validates the two files to see if any patterns are defined. If no patterns are defined, then the plug-in does not parse the Diagnostic Log file. If matching patterns are not defined, but ignore patterns are defined, then the plug-in parses every entry in the Diagnostic Log file and checks if ignore patterns are satisfied. If matching patterns are also defined, then the plug-in first parses only those entries that satisfy the matching patterns, and then for those satisfied entries, the plug-in checks if ignore patterns are satisfied.

Also, if multiple log entries having the same function name are encountered in a collection, then only one alert is generated to represent the function name. This alert is based on the last log entry with a common function name, present in the Diagnostic Log file.

Note: This feature is supported only for local monitoring, that is, when the IBM DB2 database on a host is monitored by an Oracle Management Agent that is running on the same host.

- In the IBM DB2 Database SQL Statement Performance and IBM DB2 Database Applications Lock Performance reports and the Agent Monitoring metric, in order to see the SQL statement text along with the application name, enable the instance configuration parameter `DFT_MON_STMT`. Otherwise, you may not see any data in the column.
- As part of JDBC URL, either IP Address or host name can be provided. Ensure that the host name can be resolved consistently on the network. Standard TCP tools such as "nslookup" and "traceroute" can be used to verify the host name. Validate using the following commands on Management Agent where plug-in is deployed:
 - `nslookup <hostname>`
This returns the IP address and fully qualified host name.
 - `nslookup <IP>`
This returns the IP address and fully qualified host name.

Setting Up the JDBC Driver

The JDBC driver is available from IBM, and consists of the following files that the Agent must be able to access:

- `db2jcc.jar`
- `db2jcc_javax.jar`
- `db2jcc_license_cu.jar`

To set up the IBM DB2 Universal Type 4 JDBC driver, do the following:

1. Create a `jdbcdriver` directory under `$ORACLE_HOME/sysman` and place the `.jar` files listed above in that directory.
2. Add the location of each individual driver `.jar` file to the `classpath.lst` file under the `$ORACLE_HOME/sysman/config` directory.
3. If the Agent is installed on a system that is part of an OS cluster, then you need to edit the `classpath.lst` file under the `$ORACLE_HOME/<node_name>/sysman/config` directory, where `node_name` is the name of the system where the Agent is installed.

If the `classpath.lst` file does not exist, create the file. For example, the `classpath.lst` file in a UNIX environment might appear as shown in the following example:

```
/home/usera/agent/sysman/jdbcdriver/ibm/db2jcc.jar  
/home/usera/agent/sysman/jdbcdriver/ibm/db2jcc_javax.jar  
/home/usera/agent/sysman/jdbcdriver/ibm/db2jcc_license_cu.jar
```

Configure the Management Agent to Deploy the Plug-In

To configure the Agent, you must first ensure that the user starting the Agent service belongs to the Local Administrators Group. Also, you must set the preferred credentials on all Agents where you want to deploy the plug-in. To do so, follow the instructions given in the following sections.

Assigning Advanced Privileges to User

To assign advanced privileges, do the following:

1. Locally on the Microsoft Windows node hosting the Agent, check that the user starting the Agent service belongs to the Local Administrators Group. If not, add it.
2. Open the Local Security Settings Windows Tool and give the following Advanced Privileges to the user starting the Agent service:
 - Act as part of the operating system
 - Adjust memory quotas for a process
 - Logon as batch job
 - Replace a process level token
3. Restart the Agent service if it is running.
4. Set the Preferred Credentials for the Host and the Agent in the Grid Control. For more information, see [Setting and Validating Preferred Credentials](#) on page -5.
 - The OS user set in the Preferred Credentials must belong to the Local Administrators Group.
 - This OS user must have the following Advanced Privileges:
 - Act as part of the operating system
 - Adjust memory quotas for a process

- Logon as batch job
- Replace a process level token

Setting and Validating Preferred Credentials

To set the preferred credentials on all Agents where you want to deploy the plug-in, do the following:

1. In Enterprise Manager Grid Control, click **Preferences**.
2. In the Preferences page, click **Preferred Credentials** in the left pane.
The Preferred Credentials page appears.
3. For the corresponding Target Type, for the Host target type, from the **Set Credentials** column, click the icon.
4. In the Host Preferred Credentials page, in the Target Credentials section, for the host that is running the Management Agent where the plug-in has to be deployed, specify the user name and password.
5. After setting the credentials, on the same page, click **Test**. If you test runs successfully, your credentials are set correctly.
6. Run the OS Command job for the Management Agent where the plug-in has to be deployed.
 - Log in to Enterprise Manager Grid Control.
 - Click the **Jobs** tab.
 - In the Job Activity page, from the Create Job list, select **OS Command**, and click **Go**.
 - Fill up the details required in the following pages, and click **Submit** to run the job. If the job runs successfully, your credentials are set correctly.

Using a Suitable Operating System User and Assigning Authorities and Privileges

The System Monitoring Plug-In for IBM DB2 accesses the table functions used in IBM DB2. For the plug-in to have access to the table functions, you have to use a suitable operating system user and assign this new user to a user group. The operating system user must have at least the minimum privileges. In addition, you have to assign the correct authority levels to this user.

Note: IBM DB2 users must be operating system users. IBM DB2 cannot have its own database users because it relies on the host operating system for security.

If you do not have an operating system user already created, first, create one on the host where IBM DB2 is running. Then, follow these steps to assign this user to a new or existing UserGroup.

1. Open the IBM DB2 Control Center.
2. From the tree view, select the database or database alias to which you want to connect.

3. Connect as an admin user.
4. From the tree view, select **User and Group Objects**.
5. From the right pane, select the already-created operating system user.
6. From the Authorities panel, select **Connect to Database**.
7. To verify the applied changes, try connecting to the database.

Note: These steps can also be performed from command line using IBM DB2 SQL.

Also, assign authorities and privileges for the operating system UserGroup. The authorities supported with IBM DB2 are SYSADM, SYSCTRL, SYSMOINT, DBADM, and LOAD. The SYSADM, SYSCTRL, and SYSMOINT authorities cannot be granted using the GRANT SQL statement. These special authorities can only be set from the database manager configuration file. DBADM privilege can only be granted by user at SYSADM authorization level.

SYSMON authority level is required to monitor IBM DB2. This level is required to access the table functions, such as SYSPROC.SNAPSHOT_DATABASE, which are used in IBM DB2.

Follow these steps to set SYSMON authority level to your UserGroup:

1. At the db2=> prompt, run the following commands:

```
db2=> update dbm cfg using sysmon_group USERGROUP
db2 => db2stop
db2 => db2start
```

2. To check whether the changes are effective, run the following command:

```
db2 => get dbm cfg
```

The following will be the output of the previous command:

```
Database Manager Configuration
Node type = Enterprise Server Edition with local and remote clients
.....
SYSADM group name      (SYSADM_GROUP)      =
SYSCTRL group name    (SYSCTRL_GROUP)     =
SYSMAINT group name   (SYSMAINT_GROUP)    =
SYSMON group name     (SYSMON_GROUP)      = USERGROUP
.....
```

Note: To understand how authorities and privileges are implemented in IBM DB2, access the IBM Web site.

Deploying the Plug-in


After you ensure that the prerequisites are met, follow these steps to deploy the plug-in:

1. Download the IBM DB2 Database Plug-in archive to your desktop or computer on which the browser is launched. You can download the archive from the Oracle Technology Network (OTN).
2. Log in to Enterprise Manager Grid Control as a Super Administrator.
3. Click the **Setup** link in the upper right corner of the Grid Control Home page, then click the **Management Plug-ins** link on the left side of the Setup page.
4. Click **Import**.
5. Click **Browse** and select the plug-in archive.
6. Click **List Archive**.
7. Select the plug-in and click **OK**.
8. Verify that you have set preferred credentials on all Agents where you want to deploy the plug-in.
9. In the Management Plug-ins page, click the icon in the **Deploy** column for the DB2 Database plug-in. The Deploy Management Plug-in wizard appears.
10. Click **Add Agents**, then select one or more Agents to which you want to deploy the plug-in. The wizard reappears and displays the Agent you selected.
11. Click **Next**, then click **Finish**.

If you see an error message stating that the preferred credential is not set up, go to the Preferences page and add the preferred credentials for the Agent target type.

If there are no errors, then you will see the following screen:

Figure 1 Successful Deployment



Configuring IBM DB2 for Health Indicator Metrics and Database Monitoring Metrics

The following sections explain the postinstallation configuration steps you need to perform on IBM DB2.

Configurations Required for Health Indicator Metrics

The health indicators for instance and database objects are enabled and disabled using the database manager configuration parameter -- HEALTH_MON. Then, the table functions -- HEALTH_TBS_HI, HEALTH_DB_HI, and HEALTH_DBM_HI get populated. These functions are used by the plug-in to show the alerts triggered based on the thresholds of health indicators.

Note: Enabling these settings may result in some overheads, such as CPU and memory. Therefore, follow these steps only if you want to view the Health Indicator metrics.

To enable or disable the HEALTH_MON by CLP (Command Line Processor), run the following command:

```
db2==> update dbm cfg using HEALTH_MON [on;off]
```

To check if your changes are effective, run the following command:

```
db2==> get dbm cfg
```

The following is the output:

```
.....  
.....  
.....  
Monitor health of instance and databases (HEALTH_MON) = ON  
.....  
.....  
.....
```

For more information, access the IBM Web site.

Configurations Required for Avoiding Metric Collection Errors for Database Monitoring Metrics

To avoid metric collection errors for for the "Database Monitoring" metrics, make a call to the `GET_DBSIZE_INFO` package so that the `STMG_DBSIZE_INFO` table gets created and populated with the required data.

The `GET_DBSIZE_INFO` procedure calculates the database size and maximum capacity. The calculated values are returned as procedure output parameters and cached in the `SYSTOOLS.STMG_DBSIZE_INFO` table. The procedure caches these values because the calculations are costly.

The `SYSTOOLS.STMG_DBSIZE_INFO` table is created automatically the first time the procedure runs. If there are values cached in the `SYSTOOLS.STMG_DBSIZE_INFO` table and they are current enough, as determined by the `snapshot-timestamp` and `refresh-window` values, then these cached values are returned.

If the cached values are not current enough, new cached values are calculated, inserted into the `SYSTOOLS.STMG_DBSIZE_INFO` table and returned, and the `snapshot-timestamp` value is updated. The last parameter in the `GET_DBSIZE_INFO` call is `refresh window`.

Default value `refresh window` (time difference between successive calls) is 30 minutes. If your database is growing at a faster rate, then you can set a lower value.

To make a call to `GET_DBSIZE_INFO` by CLP (Command Line Processor), run the following command:

```
db2=>CALL GET_DBSIZE_INFO(?, ?, ?, -1)
```

In this case, the `refresh window` is 30 minutes.

For more information, access the BIM Web site.

Adding Instances for Monitoring

After successfully deploying the plug-in, follow these steps to add the plug-in target to Grid Control for central monitoring and management:

1. From the Agent home page where the plug-in was deployed, select the **IBM DB2 Database** target type from the **Add** drop-down list, then click **Go**. The Add IBM DB2 Database page appears.
2. Provide the following information for the properties:

- **Name** — Name for the plug-in
- **JDBC URL** — URL name for the IBM DB2 JDBC Driver connectivity.

For example,

```
jdbc:db2://<server>:<port>/<database>
```

The JDBC URL argument represents a data source. Parameter definitions are as follows:

- **jdbc:db2** — Indicates that the connection is to a DB2 UDB server.
- **server** — Domain name or IP address of the database server.
- **port** — TCP/IP server port number assigned to the database server, which is an integer between 0 and 65535.
- **database** — Database alias, which refers to the DB2 database catalog entry on the DB2 client.

database is the database name defined during DB2 UDB (LUW) installation.

- **JDBC Driver** — (Optional) Name of the DB2 Universal JDBC Driver.

For example,

```
com.ibm.db2.jcc.DB2Driver
```

- **Username** — Valid user name for the database.

For more information, see [Using a Suitable Operating System User and Assigning Authorities and Privileges](#).

- **Password** — Password for the user.

3. Click **Test Connection** to make sure the parameters you entered are correct.
4. For Oracle Management Service version 10g Release 3 (10.2.0.3) or lower, reenter the encrypted parameters from step 2 if the connection test was successful, then click **OK**.

Note: For Oracle Management Service 10g Release 3 (10.2.0.3), if you do not reenter the encrypted parameters before clicking **OK**, you might encounter an error informing you that the login failed.

Figure 2 Add IBM DB2 Database

The screenshot shows the Oracle Enterprise Manager 10g interface for adding a new target. The page title is "Add IBM DB2 Database". At the top, there are navigation tabs for "Home", "Targets", "Deployments", "Alerts", and "Compliance". Below the navigation is a breadcrumb trail: "Enterprise Manager Configuration | Management Services and Repository | Agents".

The main configuration area is titled "Properties" and contains the following fields:

- * Name:
- Type: IBM DB2 Database

Name	Value
JDBC URL (Example : jdbc:db2://<host>:<port>/<database>)	<input type="text" value="jdbc:db2://stmp1.com:50000/TOOLSDB"/>
JDBC Driver (Optional - Default : com.ibm.db2.jcc.DB2Driver)	<input type="text" value="com.ibm.db2.jcc.DB2Driver"/>
Database Username	<input type="text" value="*****"/>
Database Password	<input type="text" value="*****"/>

Below the properties section is a "Monitoring" section with the following text: "Oracle has automatically enabled monitoring for this target's availability and performance, so no further monitoring configuration is necessary. You can edit the metric thresholds from the target's homepage." At the bottom right of the form are three buttons: "Test Connection", "Cancel", and "OK".

Note: After you deploy and configure the plug-in to monitor one or more targets in the environment, you can customize the monitoring settings of the plug-in. This alters the collection intervals and threshold settings of the metrics to meet the particular needs of your environment. If you decide to disable one or more metric collections, this could impact the reports that the metric is a part of.


Verifying and Validating the Plug-in

After waiting a few minutes for the plug-in to start collecting data, follow these steps to verify and validate that Enterprise Manager is properly monitoring the plug-in target:

1. Click the IBM DB2 Database target link from the Agent home page Monitored Targets table.

The IBM DB2 Database home page appears.

Figure 3 IBM DB2 Database Home Page



2. Verify that no metric collection errors are reported in the Metrics table.
3. Ensure that reports can be seen by selecting the **Reports** property page.
4. Ensure that configuration data can be seen by clicking the **View Configuration** link in the Configuration section. If configuration data does not immediately appear, click **Refresh** in the View Configuration page.

Upgrading the Plug-in

Follow these steps to upgrade the plug-in:

1. Download the IBM DB2 Plug-in archive to your desktop or computer on which the browser is launched. You can download the archive from the Oracle Technology Network (OTN).
2. Log into Enterprise Manager Grid Control as a Super Administrator.
3. Click the **Setup** link in the upper right corner of the Grid Control Home page, then click the **Management Plug-ins** link on the left side of the Setup page.
4. Click **Import**.
5. Click **Browse** and select the plug-in archive that you have downloaded for upgrading.
6. Click **List Archive**.
7. Select the plug-in and click **OK**.
8. Verify that preferred credentials are set on all Agents to which you want to deploy the plug-in.

9. Blackout the IBM DB2 targets for agents to which you want to deploy higher version of the plug-in. Ensure that you select immediate blackout.
10. In the Management Plug-ins page, click the icon in the **Deploy** column for the IBM DB2 plug-in. The Deploy Management Plug-in wizard appears.
11. Click **Add Agents**, then select one or more Agents to which you want to deploy the plug-in. The wizard reappears and displays the Agent you selected.
12. Click **Next**, then click **Finish**.

If you see an error message stating that the preferred credential is not set up, go to the Preferences page and add the preferred credentials for the Agent target type.
13. Remove blackout for the targets (required only if Step 9 applies).

Undeploying the Plug-in

Follow these steps to undeploy the plug-in from an Agent:

1. Log in to Enterprise Manager Grid Control as a Super Administrator.
2. Select the **Targets** tab, then the **All Targets** subtab.
3. Select the DB2 Database Plug-in target and click **Remove**. You must do this step for all targets of the specific version of the plug-in.
4. Make sure that the preferred credentials are set on the Agents where the plug-in is deployed.
5. Click the **Setup** link in the upper right corner of the All Targets page, then click the Management Plug-ins link on the left side of the Setup page. The Management Plug-ins page appears.
6. Click the icon in the **Undeploy** column for the IBM DB2 Database plug-in. The Undeploy Management Plug-in page appears.
7. Check all the Agents that are currently deployed with the DB2 Database Management plug-in and click **OK**.

You must undeploy the plug-in from every Agent in the system to completely remove it from the enterprise.
8. Select the IBM DB2 Database Management Plug-in on the Management Plug-ins page and click **Delete**.

Troubleshooting the Plug-In

For information about the troubleshooting scenarios that you might encounter while working with the System Monitoring plug-ins, see the *Enterprise Manager System Monitoring Plug-in Troubleshooting Guide* available on OTN at the following URL.

<http://www.oracle.com/technetwork/oem/grid-control/documentation/oem-091904.html>

On the OTN page, click **View Library**. Then, in the Enterprise Manager documentation library, click the **Plug-ins** tab, and look for the troubleshooting guide.

Documentation Accessibility

Our goal is to make Oracle products, services, and supporting documentation accessible to all users, including users that are disabled. To that end, our documentation includes features that make information available to users of assistive technology. This documentation is available in HTML format, and contains markup to facilitate access by the disabled community. Accessibility standards will continue to evolve over time, and Oracle is actively engaged with other market-leading technology vendors to address technical obstacles so that our documentation can be accessible to all of our customers. For more information, visit the Oracle Accessibility Program Web site at <http://www.oracle.com/accessibility/>.

Accessibility of Code Examples in Documentation

Screen readers may not always correctly read the code examples in this document. The conventions for writing code require that closing braces should appear on an otherwise empty line; however, some screen readers may not always read a line of text that consists solely of a bracket or brace.

Accessibility of Links to External Web Sites in Documentation

This documentation may contain links to Web sites of other companies or organizations that Oracle does not own or control. Oracle neither evaluates nor makes any representations regarding the accessibility of these Web sites.

Deaf/Hard of Hearing Access to Oracle Support Services

To reach Oracle Support Services, use a telecommunications relay service (TRS) to call Oracle Support at 1.800.223.1711. An Oracle Support Services engineer will handle technical issues and provide customer support according to the Oracle service request process. Information about TRS is available at <http://www.fcc.gov/cgb/consumerfacts/trs.html>, and a list of phone numbers is available at <http://www.fcc.gov/cgb/dro/trsphonenumber.html>.

System Monitoring Plug-in Installation Guide for IBM DB2 Database, Release 12 (3.4.1.1.0), Release 9 (3.4.1.0.0), and Release 8 (3.3.1.0.0)
E12777-04

Copyright © 2010, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

This software is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure the safe use of this software. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software in dangerous applications.

Oracle is a registered trademark of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

This software and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.