

Oracle® Universal Content Management

Content Integration Suite Developer Guide

10g Release 3 (10.1.3.3.3)

November 2008

Copyright © 1996, 2008, Oracle. All rights reserved.

Primary Author: Will Harris

Contributor: Adam Stuenkel

The Programs (which include both the software and documentation) contain proprietary information; they are provided under a license agreement containing restrictions on use and disclosure and are also protected by copyright, patent, and other intellectual and industrial property laws. Reverse engineering, disassembly, or decompilation of the Programs, except to the extent required to obtain interoperability with other independently created software or as specified by law, is prohibited.

The information contained in this document is subject to change without notice. If you find any problems in the documentation, please report them to us in writing. This document is not warranted to be error-free. Except as may be expressly permitted in your license agreement for these Programs, no part of these Programs may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose.

If the Programs are delivered to the United States Government or anyone licensing or using the Programs on behalf of the United States Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are "commercial computer software" or "commercial technical data" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the Programs, including documentation and technical data, shall be subject to the licensing restrictions set forth in the applicable Oracle license agreement, and, to the extent applicable, the additional rights set forth in FAR 52.227-19, Commercial Computer Software--Restricted Rights (June 1987). Oracle USA, Inc., 500 Oracle Parkway, Redwood City, CA 94065.

The Programs are not intended for use in any nuclear, aviation, mass transit, medical, or other inherently dangerous applications. It shall be the licensee's responsibility to take all appropriate fail-safe, backup, redundancy and other measures to ensure the safe use of such applications if the Programs are used for such purposes, and we disclaim liability for any damages caused by such use of the Programs.

Oracle, JD Edwards, PeopleSoft, and Siebel are registered trademarks of Oracle Corporation and/or its affiliates. Other names may be trademarks of their respective owners.

The Programs may provide links to Web sites and access to content, products, and services from third parties. Oracle is not responsible for the availability of, or any content provided on, third-party Web sites. You bear all risks associated with the use of such content. If you choose to purchase any products or services from a third party, the relationship is directly between you and the third party. Oracle is not responsible for: (a) the quality of third-party products or services; or (b) fulfilling any of the terms of the agreement with the third party, including delivery of products or services and warranty obligations related to purchased products or services. Oracle is not responsible for any loss or damage of any sort that you may incur from dealing with any third party.

Contents

Preface	v
Audience	v
Related Documents	v
Conventions	v
1 Introduction	
1.1 CIS Architecture	1-1
1.2 CIS Samples	1-2
1.3 Internationalization / Character Encoding	1-2
1.4 Deprecated FixedAPI	1-2
2 Understanding the UCPM API	
2.1 Accessing the UCPM API	2-1
2.2 UCPM API Methodology	2-2
2.3 CIS Initialization	2-2
2.3.1 Initialization	2-2
2.3.2 SCSInitializeServlet	2-3
2.4 Integration in a Web Environment	2-4
2.5 Classloading	2-5
2.5.1 Custom Class Loader	2-5
2.5.2 Classloader Usage	2-6
2.6 Object Creation	2-6
2.7 Interacting With the UCPM API	2-7
2.8 Interface IContext	2-8
2.9 Interface ICISObject	2-9
2.9.1 Property Accessors	2-9
2.9.2 Property Object Types	2-10
2.9.3 Property Collections	2-10
2.10 Adapter Configuration File	2-11
2.10.1 Adapter Element	2-11
2.10.2 Config Element	2-11
3 Understanding the SCS API	
3.1 Accessing the SCS API	3-1
3.2 Understanding the SCS API Objects	3-2

3.2.1	Interface ISCSObject	3-2
3.2.2	Interface ICISTransferStream	3-3
3.2.3	Interface ISCServerBinder	3-4
3.2.4	Interface ISCServerResponse	3-7
3.2.5	Interface ICSRequestModifier	3-7
3.3	Understanding the SCS API Servlets	3-8
3.3.1	Servlet Descriptions	3-8
3.3.2	SCS Servlet Parameters	3-9
3.3.2.1	SCSFileDownloadServlet	3-9
3.3.2.2	SCSDynamicConverterServlet	3-10
3.3.2.3	SCSDynamicURLServlet	3-10
3.3.3	Servlet Security	3-10
3.3.4	Servlets and API Interaction	3-11
3.4	Using the SCS APIs	3-12
3.4.1	SCS Search API	3-12
3.4.2	SCS File API	3-12
3.4.3	SCS Document APIs	3-13
3.4.3.1	ISCSDocumentCheckinAPI	3-13
3.4.3.2	ISCSDocumentCheckoutAPI	3-14
3.4.4	SCS Workflow API	3-14

Index

Preface

The Oracle Content Integration Suite (CIS) Developer Guide provides general information on CIS, details on the Universal Content Universal Content and Process Management API (UCPM API), an explanation of the various service APIs (SCS, SIS, and Common), information on extending commands, and instructions for migrating from previous versions.

Audience

This guide is intended for application developers and programmers. It includes conceptual and other information about the UCPM API, describes command invocation and execution, and explains how commands can be extended.

Related Documents

For more information, see the following documents in the Oracle Content Integration Suite (CIS) documentation set:

- Oracle Content Integration Suite (CIS) Release Notes
- Oracle Content Integration Suite (CIS) Administration Guide

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.
/	This guide uses the forward slash (/) to separate directories. Depending on your operating system, you may need to change the separation markers when defining directories.

Introduction

The Content Integration Suite (CIS) API offers access to Oracle Content Server by exposing the content server services and data in a unified object model. The UCPM API is modeled into a set of Services APIs, which are API calls that communicate with the target server and the returned value objects from the server.

This chapter contains the following sections:

- ["CIS Architecture"](#) on page 1-1
- ["CIS Samples"](#) on page 1-2
- ["Internationalization / Character Encoding"](#) on page 1-2
- ["Deprecated FixedAPI"](#) on page 1-2

1.1 CIS Architecture

CIS has a layered architecture that allows for its deployment in a number of different configurations. The architecture, at its core, is based on the standard J2EE Command Design Pattern. The layers on top of the commands provide the APIs that are exposed to the end user.

This version of CIS uses the Universal Content and Process Management API (UCPM API) which uses the SCS API for communication to the content server. The SCS API wraps communication from the content server into an object model that allows access to the individual object metadata.

The UCPM API allows application developers to focus on presentation issues rather than being concerned with how to access content server services (IdcCommand services). The UCPM API comprises a set of command objects that encapsulate distinct actions that are passed to the UCPM API and then mapped to the content server. These commands include common functions such as search, checkout, and workflow approval. Each command is tied to one or more service calls. The UCPM API command objects have been developed in accordance with the J2EE Command Design Pattern.

This infrastructure is deployable in any J2EE-compliant application server or stand-alone JVM application. When deployed, the UCPM API will leverage the features in the environment, whether this is a J2EE application server or non-J2EE.

The UCPM API encapsulates content server business logic and validates the parameters of the incoming calls. The UCPM API handles communication to the content server, encapsulates socket communication logic (opening, validating, and streaming bits through the socket), and provides a strongly typed API to the available services.

1.2 CIS Samples

The CIS distribution file includes samples and Ant build scripts. In order for the samples to produce logs you must configure the development environment to include the logging file in the Classpath.

These samples are included:

Directory	Description
Samples/Code Examples	Samples that show how to execute various pieces of the UCPM API.
Samples/StellentWebSample	A sample web application that demonstrates the SDK working with the SCS, SIS, and CIS APIs.

1.3 Internationalization / Character Encoding

We recommend that encoding for CIS be set to the same encoding as the Java Virtual Machine running Content Server. However, if CIS is communicating with multiple instances of Content Server in different languages, the `ISCContext.setEncoding` method can be used to set the encoding to match that of the JVM running CIS.

1.4 Deprecated FixedAPI

The Fixed API available in previous releases of CIS for communication with the Image Server has been deprecated. Calling `getFixedAPI()` throws an error.

Understanding the UCPM API

The Universal Content Universal Content and Process Management API (UCPM API) offers access to servers by exposing their services and data in a unified object model. The UCPM API is modeled into a set of Services APIs that communicate with the target server.

This chapter contains the following sections:

- ["Accessing the UCPM API"](#) on page 2-1
- ["UCPM API Methodology"](#) on page 2-2
- ["CIS Initialization"](#) on page 2-2
- ["Integration in a Web Environment"](#) on page 2-4
- ["Classloading"](#) on page 2-5
- ["Object Creation"](#) on page 2-6
- ["Interacting With the UCPM API"](#) on page 2-7
- ["Interface IContext"](#) on page 2-8
- ["Interface ICISObject"](#) on page 2-9
- ["Adapter Configuration File"](#) on page 2-11

Note: Refer to the JavaDocs for information on the Class/Interface, Field, and Method descriptions (located in the /docs/cis-javadoc.zip file).

2.1 Accessing the UCPM API

The UCPM API offers access to servers by exposing their services and data in a unified object model. The UCPM API is modeled into a set of Services APIs, which are API calls that communicate with the target server, and into ICISObject objects, which are the value objects returned from the server.

The UCPM API is available on the ICISApplication class via the getUCPMAPI() method. The getUCPMAPI() method returns a reference to the IUCPMAPI object, allowing access to all UCPM API objects. Public interface IUCPMAPI is the locator for the getActiveAPI object; **getActiveAPI()** returns a reference to the SCSActiveAPI object. The SCS API classes communicate with and handle content stored on the content server.

2.2 UCPM API Methodology

The UCPM API is stateless; all method calls pass in the necessary state to the method. This means that you can share the reference to the CISApplication class across threads.

- ISCSContext for the SCS API. The interface ISCSContext is the context object used when communicating with the content server.
- ICISCommonContext for calling some of the CIS APIs. The interface ICISCommonContext identifies which adapters to query and what user information to use.

The first parameter for all methods is an IContext bean. The IContext bean holds context information, such as username and session ID, that is used in the underlying service APIs to identify the user invoking the given command.

The UCPM API is a service-oriented API that returns value objects, implemented as ICISObject objects (name changed from the 7.6 API). However, calling methods on the value objects themselves do not modify content on the server; one must call the UCPM API and pass in the value object as a parameter before the changes can be applied.

Example:

```
SCSActiveAPI activeAPI = m_cisApplication.getUCPMAPI ().getActiveAPI ();
ISCSDocumentID documentID = (ISCSDocumentID) m_cisApplication.getUCPMAPI ().
    createObject(ISCSDocumentID.class);
documentID.setDocumentID("10");
ISCSDocumentInformationResponse docResponse =
    activeAPI.getDocumentInformationAPI ().
        getDocumentInformationByID(m_context, documentID);
ISCSContent content = docResponse.getDocNode();

// call does not change object on server
content.setTitle ("New Title");

// now item is updated on server after this call
activeAPI.getDocumentUpdateAPI ().updateInfo (m_context, content);
```

2.3 CIS Initialization

Content Integration Suite (CIS) is initialized by accessing the CISApplicationFactory class, which resides in the com.stellent.cis.impl package.

This section contains the following topics:

- ["Initialization"](#) on page 2-2
- ["SCSInitializeServlet"](#) on page 2-3

2.3.1 Initialization

CIS initialization should happen once per application. The CIS APIs are stateless and therefore the initialized CISApplication instance can be safely shared between threads.

To initialize CIS, a number of properties must be defined. The cis.config.type should be *server* and the cis.config.server.type should be *standalone*. The adapter configuration file contains XML-formatted configuration information for communicating with the content servers.

Initialization Examples

Initializes the system and reads the adapterconfig.xml file from the classpath:

```

cis.config.type=server
cis.config.server.type=standalone
cis.config.server.adapterconfig=classpath:/adapterconfig.xml

```

Code example:

```

ICISApplication application;
URL xmlRes = new File ("adapterconfig.xml").toURL();
Properties properties = new Properties();
properties.setProperty(ICISApplication.PROPERTY_CONFIG_TYPE, "server");
properties.setProperty(ICISApplication.PROPERTY_CONFIG_SERVER_ADAPTER_CONFIG,
    xmlRes.toExternalForm());

properties.setProperty(ICISApplication.PROPERTY_CONFIG_SERVER_TYPE, "standalone");
application = CISApplicationFactory.initialize(properties);

```

Property Definitions

The properties are defined in the following table.

Property	Description
<code>cis.config.type</code>	Should be set to server.
<code>cis.config.server.type</code>	Should be set to standalone.
<code>cis.config.server.adapterconfig</code>	The URL pointing to the adapter configuration file. In addition to standard URLs, this can be in classpath form (classpath:/) or file form (file:/)
<code>cis.config.server.tmporarydirectory</code>	The location of the temporary directory used for file transfers, streaming, and file caching.

2.3.2 SCSInitializeServlet

The `SCSInitializeServlet` is a convenient way to initialize a `CISApplication` instance from within a web application. Any of the properties described can be used by the `SCSInitializeServlet`. The `SCSInitializeServlet` can be configured externally via a properties file. The `cis.initialization.file` property can be set with a path (either a web-relative path or a classpath reference), to a property file containing the initialization properties. This allows you to easily externalize the initialization to a properties file.

By default, if `SCSInitializeServlet` finds no properties in the `web.xml` file, it will attempt to load a properties file from the WAR and then from the classpath using the default value `/cis-initialization.properties`. Thus, if you place a file called `cis-initialization.properties` in your classpath (that is, in the same directory as the `adapterconfig.xml` file), that file will be read during startup.

This properties file can hold all the standard initialization properties as defined in the `CISApplication` class. This allows us to move the configuration of the how CIS initializes outside the scope of the EAR/WAR file.

Server Property Definitions

The server properties are defined below. The defaults can be overridden by creating a file named `cis-initialization.properties` and saving the file to the `server-ear` directory of

the unbundled CIS distribution file (this is the directory containing the adapterconfig.xml file).

Property	Description
cis.config.type	Must be set to server (default).
cis.config.server.adapterconfig	The URL pointing to the adapterconfig.xml file. In addition to standard URLs, this can also be in classpath form (i.e. classpath:/)
cis.config.server.type.options.ejb=true	Default is true (EJBs enabled).
cis.config.server.type.options.rmi=true	Default is true (MI enabled).

Initialization Process

At startup, the `SCSInitializeServlet` servlet begins the CIS server initialization process. It attempts to load various properties from the `web.xml` file and classpath (i.e., `cis-initialization.properties`). It then passes those properties to the static method `CISApplicationFactory.initialize(...)`. This section describes the order of operation.

SCSInitialize init(ServletConfig)

Called by the web application container during initialization of the web application.

1. Load properties from `web.xml`.
2. Load properties from classpath: `/cis-initialization.properties`.
3. Call `CISApplicationFactory.initialize(properties)`.
4. Via the `CISWebHelper` class, it sets the `CISApplication` and the command application instance as an attribute on the servlet context.

CISApplicationFactory initialize(properties)

Called by the `init(...)` method of an object instance of `SCSInitialize`. Calls `CISApplicationFactory.initializeCisApplication(properties)`.

CISApplicationFactory initializeCisApplication(properties)

Determines if CIS should be started in client or server mode. Calls `CISApplicationFactory.initializeServer(properties)`.

CISApplicationFactory initializeServer(properties)

Called by `CISApplicationFactory.initialize(properties)`.

1. Creates the adapter config URL (used to eventually load the adapterconfig).
2. Loads the `IsolatedJarClassLoader`.
3. Calls `CISApplication.initialize(properties)`.

2.4 Integration in a Web Environment

This is what you would put in the `web.xml` if you wanted the `SCSInitializeServlet` to startup, and register the CIS application:

```
<servlet id="scsInitialize">
  <servlet-name>scsInitialize</servlet-name>
  <display-name>SCS Initialize Servlet</display-name>
  <servlet-class>com.stellent.cis.web.servlets.SCSInitializeServlet
  </servlet-class>
```

```
<load-on-startup>1</load-on-startup>
</servlet>
```

If we add a new JavaServer Page called `search.jsp`, it would look like the following:

```
<!-- JSTL tag library --%>
<%@ taglib uri="/WEB-INF/tlds/c.tld" prefix="c" %>

<!-- CIS Application object placed in servlet context by the SCSInitialize
servlet. Get the CIS Application and make a query --%>

<%
ICISApplication cisApplication =
    (ICISApplication) request.getSession().getServletContext().
        getAttribute ("CISApplication");
ISCSSearchAPI searchAPI =
    cisApplication.getUCPMAPI ().getActiveAPI ().getSearchAPI ();

// create a context
ISCSContext context =
    cisApplication.getUCPMAPI ().getActiveAPI ()._createSCSContext ();
    context.setUser ("sysadmin");

// execute the search
ISCSSearchResponse response =
    searchAPI.search (context, "dDocAuthor <substring> 'sysadmin'", 20);
%>
<!-- model the search results as desired -->
```

The `SCSInitializeServlet` places the initialized `CISApplication` class as an attribute in the `javax.servlet.ServletContext` with the name `CISApplication`. The `CISApplication` instance is available to the entire web application and is thread-safe; the one instance can be shared across the application.

2.5 Classloading

The UCPM 8.0.0 API uses a custom class loader to isolate dependencies on specific libraries from any application that uses the CIS API. Refer to the Java 2 Platform API specification for more information:

<http://java.sun.com/j2se/1.4.2/docs/api/java/lang/ClassLoader.html>

This section contains the following topics:

- ["Custom Class Loader"](#) on page 2-5
- ["Classloader Usage"](#) on page 2-6

2.5.1 Custom Class Loader

Our implementation of this paradigm is found in the `com.stellent.cis.impl.IsolatedJarClassLoader` object. This custom class loader allows for a jar to have a nested set of JAR files that serve as the library. This is the structure of the nested JAR files:

```
+ cis-application-8.0.0.jar
  +-- com/stellent/cis/...
  +-- META-INF
  +-- lib/
      +-- spring-1.1.5.jar
```

```
+++ log4j-1.0.3.jar  
+++ ...
```

All libraries that live in the /lib directory will be the classpath for the CIS objects. The classloader will query this local directory first before loading files from the parent classloader.

However, all of the JAR files cannot be isolated as the consuming client needs to have access to some API classes so they can be imported into their application space. Therefore only our interfaces are exposed into the application space; keeping our implementation and associated dependencies isolated. Since the class loader for the dependencies and implementation has access to the parent loader, it can access the same version of the interfaces as the application using the APIs. This also implies that a client will only be able to access the interfaces of the UCPM APIs. Any attempt to create an implementation class using the new keyword will result in a `ClassNotFoundException`.

2.5.2 Classloader Usage

To use this classloader, use the new `com.stellent.cis.impl.CISApplicationFactory` object to initialize the system. This object will automatically detect and use the `IsolatedJarClassLoader` if required. This means that you can still deploy CIS in the original format, with all the class files and libraries at the application level, if you so desire.

In the current version, CIS only needs the `cis-client-8.0.0.jar` file in the classpath; no other libraries are needed. Once `cis-client-8.0.0.jar` is in the application classpath, you initialize CIS using the following code:

```
// the initialization properties (as defined in ICISApplication)  
Properties properties = new Properties ();  
ICISApplication cisApplication = CISApplicationFactory.initialize(properties);
```

Once you have a reference to `com.stellent.cis.ICISApplication`, you can interact with the APIs. The difference is now you only have access to interface objects (everything in `com.stellent.cis.client`) and not the implementation objects.

If you implement custom commands, your public interfaces will also need to be in the classpath, and the implementation classes packaged in the `cis-client-8.0.0.jar`.

2.6 Object Creation

The UCPM 8.0.0 API uses a customized classloader to hide library dependencies and implementation classes. Only the client interface classes are exposed to the user. However, this implies that you cannot use the new keyword to instantiate UCPM API objects. Therefore, in the UCPM API framework, use the generic `_create` methods available on the `IUCPMAPI` object to tell the system to instantiate an instance of the given object.

Because objects are mutable and only the interfaces are exposed; use the `createObject` method and set the properties that you need:

```
ISCSDocumentID docID =  
    (ISCSDocumentID)ucpmAPI.createObject(ISCSDocumentID.class);  
docID.setDocumentID("20");
```

2.7 Interacting With the UCPM API

With an initialized CISApplication instance, the `getUCPMAPI ()` method (of the CISApplication object) returns a reference to the IUCPMAPI object, allowing access to all UCPM API objects. The interface IUCPMAPI is the locator for the various API objects in the UCPM API. The IUCPMAPI object has methods to get references to the Active API; `getActiveAPI ()` returns a reference to the SCSActiveAPI object for communicating with the content server. This allows you to access the necessary APIs and begin making calls through the UCPM API to the target server.

Calling API Objects Using Newly Instantiated ICISObject Objects

Many UCPM API calls take in an ICISObject or an interface that inherits from ICISObject. For example, in the ISCSDocumentInformationAPI (SCS API) the `getDocumentInformationByID ()` method takes as a parameter a ISCSDocumentID object.

The fully qualified method name is:

```
ICISApplication.getUCPMAPI ().getActiveAPI ().getDocumentInformationAPI ()
```

In such cases, to obtain a reference to a valid object to pass in as a parameter, you either can retrieve the object reference from another ICISObject or create a new instance of the ICISObject using the generic `createObject` method available on the UCPMAPI. In CIS 8.0.0, a customized classloader is used to hide our library dependencies and implementation classes. Only our client interface classes are exposed to the user. However, this implies that you cannot use the `new` keyword to instantiate UCPM API objects. Therefore, in the CIS API framework, you use the generic `create` method available on the IUCPMAPI object to tell the system to instantiate an instance of the given object. The `createObject` method will let you create a new instance of any ICISObject.

For example, if you wanted to query for document information, but only had the document ID, you would do the following:

```
ISCSDocumentInformationAPI documentInfoAPI =
    m_cisApplication.getUCPMAPI ().getActiveAPI ().getDocumentInformationAPI ();

// create the document ID
ISCSDocumentID documentID =
    (ISCSDocumentID) m_cisApplication.getUCPMAPI ().
        createObject (ISCSDocumentID.class);
    documentID.setDocumentID("12345");

ISCSDocumentInformationResponse docResponse =
    documentInfoAPI.getDocumentInformationByID(m_context, documentID);
```

For any API that requires an ICISObject, you can use the `createObject` method that allows you to create a new instance of the API object. The `createObject` methods is a client-side method; it does not make a call to the target server. It is to be treated as a *constructor* for the ICISObject implementations.

If you needed to build up a more complex object such as a new content item to be checked into the content server, you would need to create several objects and populate the data:

```
// Create an empty content object
ISCSContent content =
    (ISCSContent) m_cisApplication.getUCPMAPI ().createObject (ISCSContent.class);

// Create an empty content ID object, and then give it a content ID
```

```
ISCSCContentID contentID = (ISCSCContentID) m_cisApplication.getUCPMAPI ().
    createObject(ISCSCContentID.class);
contentID.setContentID("my_document");

// Set all of the properties of the content item required for check in
content.setContentID(contentID);
content.setAuthor (context.getUser ());
content.setTitle ("Document Title");
content.setSecurityGroup ("Public");
content.setType ("ADACCT");
content.setProperty ("xCustomProperty", "Value for custom property");
```

2.8 Interface IContext

The interface IContext is the generic context used for communication with the Command APIs. This interface handles contextual information to determine the current caller identity, the target adapter, etc.

The context should be populated with the username and adapter name. The adapter name is determined by the adapterconfig.xml file and the username can be any valid user ID for the target server.

IContext has the sub-interfaces SCSCContext (ISISContext extends the IContext interface); **ISCSCContext** is the context object used for the SCS APIs and represents a users operating context when communicating with the content server.

The context object can be created by using the `_create` method. Thus, ISCSCContext can be created from SCSCActiveAPI.

```
// create an ISCSCContext
ISCSCContext context =
    m_cisApplication.getUCPMAPI ().getActiveAPI ()._createSCSCContext ();
```

Once the context is created, it should be populated with a username and the adapter name. This can be done by using the accessor methods on the IContext bean.

```
context.setUser ("sysadmin");
context.setAdapterName ("myadapter");
```

The CIS API will take either an ICISCommonContext or an IContext object. ICISCommonContext is a special kind of context that is used as a container for ISCSCContext and ISISContext. It is required in APIs that federate information between a number of different adapters; it identifies which adapters to query and what user information to use. In instances where the call only operates against one adapter at a time, a single IContext is required.

```
// create an ICommonContext
ICISCommonContext m_commonContext =
    m_cisApplication.getUCPMAPI ().getCommonAPI ()._createCommonContext ();
```

Once the ICISCommonContext adapter is created, multiple adapters can be added to it. This is done using the ICISCommonContext.addContext() method. Any number of adapters can be added; all the adapters added to the ICISCommonContext are then used individually during a Common API call.

The same ISCSCContext object can be used for multiple queries and across threads. In a web application context, the easiest method is to add the IContext object to the session and retrieve it from the session for each query.

An sample web application has been provided (located in /SDK/Samples/WebSample) that has a login method that first validates the username

against the content server and, if successful, adds the IContext object to the HttpSession object. Refer to the LoginActionHandler class in the src/com/stellent/sdk/web/sampleapp/handlers/login directory for more details.

2.9 Interface ICISObject

The interface ICISObject is the base interface for all objects with metadata in the UCPM API. Thus, all UCPM API objects are inherited from ICISObject. The interface ICISObject allows for the retrieval and setting of the object properties. The objects returned from calls to the UCPM API are value objects in the form of beans (reusable software components) that encapsulate data from the server call, not live objects. Updating or modifying the objects in any fashion will not affect server data; only by directly calling a method on a given UCPM API can the server data be modified.

This section contains the following topics:

- ["Property Accessors"](#) on page 2-9
- ["Property Object Types"](#) on page 2-10
- ["Property Collections"](#) on page 2-10

2.9.1 Property Accessors

Most implementations of ICISObject have their own specific property accessor methods. However, all properties can be retrieved by calling the `getProperty ()` method on the ICISObject. The `ICISObject.getProperty ()` method will return an `ICISProperty` object. From this object you can get the property value or property information using these methods:

- **getValue()** returns the property value. If the property has a null value, calling `getValue ()` will result in a null reference.
- **getDescriptor()** returns the property descriptor that describes the contents of the property value.

```
// use the response object from the previous example - retrieve the content object
ISCSContent content = docResponse.getDocNode ();

// get the title property
String title = content.getTitle ();

// get the title by using the ICISObject getProperty method
title = content.getProperty ("title").getValue ().getStringValue ();
```

The ICISObject property methods may throw a `PropertyRetrievalException` if an error occurs during the lookup of a given property. Since the `PropertyRetrievalException` is a `RuntimeException` it does not have to be caught directly in your code. Common cases for the exception to be thrown is when a property is asked for but does not exist or when the property value contains invalid data. You can catch this exception and query the exception class for more details on the specific reason for the error.

`ISCSProperty` also allows for setting property values back into the property object. To do this, you can use an appropriate set method or call `setProperty ()` and pass in the bean property name (both are valid and both will set the property value on the target object).

```
// set the title - using the content object from the previous example
content.setTitle ("My New Title");
```

```
// set using the setProperty method
content.setProperty ("title", "My New Title");
```

2.9.2 Property Object Types

A property object type is determined by the return value of the property method on the ICISObject. When using the generic getProperty() method, the ISCSPropertyValue has methods to get both the value of the property and the value as a specific object type (e.g., boolean, float, long, etc.).

The ISCSPropertyValue is retrieved via the getValue() method on the returned ISCSProperty object.

When setting a property via the generic setProperty() method, it is important that the property value passed into the method is of the correct type or can be converted to the appropriate type via simple BeanUtils property conversion.

Apache BeanUtil is a utility for populating bean properties from the org.apache.commons project.

If we take a look at the ISCSContent object, the property readOnly is type boolean. Therefore, in the following example, the first three methods will successfully set the property value and the last method will not:

```
// correct
content.setReadOnly (true);
content.setProperty ("readOnly", Boolean.TRUE);
content.setProperty ("readOnly", "true");

// incorrect
content.setProperty ("readOnly", "not a boolean");
```

Since the setProperty () method takes an object as the second parameter, the boolean encapsulation must be used. Also, as mentioned, the method uses the BeanUtils property conversion and therefore the string *true* converts to the boolean value TRUE. As shown in the example above, passing a property value that cannot be converted (e.g., not a boolean) will result in an exception.

2.9.3 Property Collections

The available list of properties can be retrieved using the getProperties() method on the ICISObject interface. This will return all of the available properties for a given object.

```
// using the content item from the previous example
Collection properties = content.getProperties ();

// iterate through the collection
for (Iterator it = properties.iterator (); it.hasNext (); ) {
    ISCSProperty property = (ISCSProperty)it.next ();
    String name = property.getDescriptor ().getName ();
    ICISPropertyValue value = property.getValue ();
    if (value != null) {
        System.out.println (name + " = " + value.getStringValue ());
    }
}
```

2.10 Adapter Configuration File

The adapter configuration file (adapterconfig.xml) contains XML-formatted configuration information for communicating with your content server instance. It specifies for the CIS layer which servers to open communications with.

A single connection to a server is called an adapter; any number of adapters can be configured in the adapterconfig.xml file. The adapterconfig.xml file is required to initialize the CISApplication instance.

If your CIS instance is deployed in a Web environment in server mode, you can use the CIS Administration Application to configure an adapter:

1. Browse to the CIS Administration Application (<http://localhost:port/cis-admin>).
2. Click **Adapter Configuration**.
3. Click **Create new SCS Adapter** and enter the appropriate values. These will vary, depending on your installation.
4. If you need assistance, click **Help**.

Refer to "Secure Socket Layer (SSL) Communication" in the CIS Installation Guide for information on enabling SSL communication.

This section contains the following topics:

- ["Adapter Element"](#) on page 2-11
- ["Config Element"](#) on page 2-11

2.10.1 Adapter Element

Each adapter configuration is a separate element in the XML markup. The adapter element has four attributes as shown in the following table:

Adapter Attributes	Description
type	Should be <i>scs</i> for a connection to a content server.
default	If true, then this is the default adapter for this type; only one default adapter for a given type is allowed.
name	The adapter name.

A sample adapter element is shown below:

```
<adapter type="scs" default="true" name="myadapter">
```

2.10.2 Config Element

Within the config element is a set of property elements that define the adapter-specific properties. These configuration elements are explained below.

SCS Adapter Configuration Elements

An SCS adapter communicates with the content server. The configuration element for the SCS adapter has four general attributes as shown in the following table:

Property Name	Description
post	The port of the content server (usually 4444).

Property Name	Description
host	The hostname or IP address of the content server.
type	<p>These values may be used:</p> <p>socket: Uses the content server socket communication layer.</p> <p>mapped: Uses shared directories to transfer the files for file upload and download.</p> <p>web: Uses HTTP requests to transfer files; requires a content server username and password for Basic HTTP Authentication (file download only).</p>

A sample SCS configuration element is shown below:

```
<adapter name="myadapter" type="scs" default="true">
  <config>
    <property name="host">localhost</property>
    <property name="port">4444</property>
    <property name="type">socket</property>
    <property name="version">75</property>
  </config>
  <beans template=
    "classpath:/META-INF/resources/adapter/adapter-services-scs.xml"/>
</adapter>
```

By default, the content server socket communication layer is used to stream files to and from the content server. However, for high-volume check in or file retrieval, you can set the **mapped** or **web** optimized file transfer options.

A mapped transfer loads the files from a shared directory on the content server; this results in much faster file transfers and does not tie up a socket that could be used for other requests. To use mapped transfer, you must define these properties:

Property Name	Description
contentServerMappedVault	The content server vault directory as seen from the application server.
appServerMappedVault	The application server vault directory as seen from the content server.

A web transfer uses HTTP requests to the content server web server to download files. To use web transfer, you must define these properties:

Property Name	Description
contentServerAdminID	The content server administrator ID to use to authenticate against the content server.
contentServerAdminPassword	The content server administrator password to use to authenticate against the content server. This password is encrypted.

A sample SCS configuration element using web transfer is shown below:

```
<adapter type="scs" default="true" name="myadapter">
  <config>
    <property name="port">4444</property>
    <property name="host">localhost</property>
    <property name="type">web</property>
  </config>
</adapter>
```

```
<property name="contentServerAdminID">sysadmin</property>  
  <property name="contentServerAdminPassword">idc</property>  
</config>  
</adapter>
```

Understanding the SCS API

The UCPM API is modeled into a set of Services APIs, which are API calls that communicate with the content server.

This chapter contains the following sections:

- ["Accessing the SCS API"](#) on page 3-1
- ["Understanding the SCS API Objects"](#) on page 3-2
- ["Understanding the SCS API Servlets"](#) on page 3-8
- ["Using the SCS APIs"](#) on page 3-12

Note: Refer to the JavaDocs for information on the Class/Interface, Field, and Method descriptions (located in the /docs/cis-javadoc.zip file).

3.1 Accessing the SCS API

The UCPM API is available on the CISApplication class via the getUCPMAPI () method. The getUCPMAPI () method returns a reference to the IUCPMAPI object, allowing access to all UCPM API objects. Public interface IUCPMAPI is the locator for the SCS, SIS, and CIS API objects. The SCS API is available via getActiveAPI (), which returns a reference to the SCSActiveAPI object.

The fully qualified method name is:

```
CISApplication.getUCPMAPI ().getActiveAPI ()
```

The SCS API comprises:

- **ISCSSearchAPI:** This is the command API implementation of the search commands.
- **ISCSFileAPI:** Deals with the retrieval of files, and the dynamic conversions of files, from the content server.
- **ISCSWorkflowAPI:** Deals with the workflow commands such as approval and rejection, viewing a user's workflow queue, and interacting with the content server workflow engine.
- **SCS Document APIs (ISCSDocumentCheckinAPI and ISCSDocumentCheckoutAPI),** which deal with active content in the content server, including the checking in and out of content, content information, and the deletion of content.

- Various APIs for the implementation of the administrative commands, component commands, etc.

The interface `ICommandFacade` is the entry point into the command interface. It allows for interaction with the command layer, including command retrieval, registration, and execution. Commands are referenced by name, where a name can be any string. A name consisting of the dot character (".") will be treated in a hierarchy, where the first segment is the top-level category, and the next segment is the second-level category, etc. Commands can either be retrieved by their full command name or by browsing all available commands.

The fully qualified class name is

```
com.stellent.command.ICommandFacade
```

Example using `ISCSDocumentCheckinCommandAPI`:

```
ISCSDocumentCheckinCommandAPI commandAPI =
    (ISCSDocumentCheckinCommandAPI)m_commandFacade.
    getCommandAPI ("document.checkin");
```

3.2 Understanding the SCS API Objects

The SCS API is responsible for formulating requests to the content server. SCS API calls translate into one or more IDC Service (Content Server Service) calls.

This section contains the following topics:

- ["Interface ISCSObject"](#) on page 3-2
- ["Interface ICISTransferStream"](#) on page 3-3
- ["Interface ISCServerBinder"](#) on page 3-4
- [Table 3.2.4, "Interface ISCServerResponse"](#)
- ["Interface ISCSRequestModifier"](#) on page 3-7

3.2.1 Interface ISCSObject

The `ISCSObject` is the base interface for all objects in the SCS API. It inherits from `ICISObject` and adds some specific functionality relative to the content server objects. It allows access to the `ISCServerResponse` object that created the object, and it also allows access to a collection of properties that have been modified since the object was initialized via the `getModifiedProperties ()` method.

The `ICISObject` class name is new for UCPM 8.0.0 API.

`ISCSObject` objects have the concept of native property names. Specifically, properties that are available on `ISCSObject` are available by two different names: the Java property name and the content server native name. For example, to get the title of a `ISCContent` item, the following three methods are equal:

```
String title = content.getTitle ();
title = content.getProperty ("title").getValue ().getStringValue ();
title = content.getProperty ("dDocTitle").getValue ().getStringValue ();
```

The content server supports a metadata model that can be extended. `ISCSObject` objects can have more properties than those exposed via the `getProperty ()` methods. The `ISCSObject` implementations expose the most common properties, but other properties, such as the extended metadata, are only available via the `getProperty ()`

method. Also, the `getProperties ()` method will list all the properties on the object, including properties without a corresponding **getter** or **setter** method.

```
for (Iterator it = content.getProperties ().iterator (); it.hasNext (); ) {
    ISCSProperty property = (ISCSProperty)it.next ();
    ISCSPropertyDescriptor descriptor = property.getActiveDescriptor ();
    if (descriptor.isBeanProperty ()) {
        System.out.println ("Property is available via get or set: " +
            property.getDescriptor().getName ());
    } else {
        System.out.println ("Property is a hidden or extended property: " +
            property.getDescriptor().getName ());
    }
    System.out.println ("Native property name: " + descriptor.getNativeName ());
}
```

The properties returned from `ISCSObject` implement the `ISCSProperty` interface, which adds the `getActiveDescriptor ()` method. The `ISCSPropertyDescriptor` adds the properties *beanProperty* and *nativeName* to the available properties on an item.

The *beanProperty* property determines if the current property object has an available **getter** or **setter** method; if the property is false, this property object is available only via the `getProperty ()` method.

The *nativeName* property returns the content server property name for the given property.

Date Objects

Date fields in the SCS API are handled as Java Date objects in Coordinated Universal Time (UTC time). All dates passed into the various properties of `ISCSObject` must be in UTC time. All date objects returned from the SCS API are in UTC time and need to be converted into the appropriate time zone for the particular application.

```
Date releaseDate = content.getReleaseDate ();

// convert from UTC time to Pacific Time Zone
Calendar calendar = Calendar.getInstance ();
calendar.setTime (releaseDate);
calendar.setTimeZone (TimeZone.getTimeZone ("America/Los_Angeles"));
// use calendar to display date...
```

3.2.2 Interface `ICISTransferStream`

File streams to and from the content server have changed. In an effort to keep with the interface-only approach to the CIS APIs, all streams are sent via the `ICISTransferStream` interface. The interface represents the actual physical stream object and additionally some metadata, including filename, content length and mime-type. Since the `ICISTransferStream` is an interface, it cannot extend `InputStream` directly. Therefore, when using this object, you must first obtain the stream via a call to `ICISTransferStream.getStream()` and then manipulate the stream appropriately.

Some commands that in previous versions would return an `InputStream` now return `ICISTransferStream` objects. For example, if calling `getFile()` in the FileAPI, to access the stream from the content server, your code would look like:

```
ICISTransferStream transferStream = fileAPI.getFile (context, documentID);
InputStream inputStream = transferStream.getInputStream();
```

The implementation of `ICISTransferStream` contains all the necessary plumbing to transfer the stream to and from the command client to command server. Since

InputStream objects are not directly serializable, it does some extra work to put streams into places where the server can access them. All of the logic is hidden from the user of the API.

The stream instance can be obtained from the root IUCPMAPI interface using the method `createTransferStream`. That returns an empty instance of the stream container, which you can then use the accessor methods to set the stream properties. For example, below we create a transfer stream and point it at a local file:

```
// create the stream implementation
ICISTransferStream transferStream = ucpmAPI.createTransferStream ();

// point it at a file
transferStream.setFile (new File ("mytestdoc.doc"));
```

If you had a stream in memory already rather than a file handle, and you wanted to check in the content in that stream into the content server, you would need to specify all of the attributes for the stream such as a filename, content type, and the length of the stream.

```
ICISTransferStream transferStream = ucpmAPI.createTransferStream ();
transferStream.setFileName ("sample.txt");
transferStream.setInputStream (inputStream);
transferStream.setContentType ("text/plain");
transferStream.setContentLength (length);
checkinAPI.checkinFileStream (context, content, transferStream);
```

3.2.3 Interface ISCSServerBinder

The 8.0.0 API provides a new object, `ISCSServerBinder`, which is the root object used for all communication to and from the content server. The `ISCSServerBinder` object encapsulates a message both to and from the content server. It is a collection of properties, result sets, files, option lists and other specific type of information needed by the content server.

All API calls into the content server will create an instance of the `ISCSServerBinder`. Each API call, for example `ISCSSearchAPI.search()`, will use the supplied `ISCSObject` parameters to populate a binder and possibly add in other particular information. Likewise, all responses from the content server that are not streams are `ISCSServerResponse` objects which extend `ISCSServerBinder`.

As all `ISCSObject`s are collections of arbitrary metadata, the `ISCSServerBinder` is a collection of a number of objects metadata contained within one object. A particular `ISCSServerBinder` might contain the metadata for a content server query (see `ISCSSearchQuery`), metadata concerning a piece of content, and a list of objects dealing with user data. As each `ISCSObject` contains the particular metadata for its object, the `ISCSServerBinder` is responsible for the metadata of many objects.

Properties

As `ISCSServerBinder` extends the core `ISCSObject` interface, it has the ability to get and set arbitrary properties via the `getProperty` and `setProperty` methods. These arbitrary properties are usually where arguments for a particular content server are placed. They can be added directly, via the `setProperty` method as shown in the following code example.

```
// create an empty binder
ISCSServerBinder binder =
    (ISCSServerBinder)getUCPMAPI ().createObject (ISCSServerBinder.class);
```

```
// set some properties
binder.setProperty ("dDocTitle", "test");
binder.setProperty ("dSecurityGroup", "Public");
```

Alternatively, properties can be set using the `mergeObject` functionality available on the `ISCSObject` interface. The following example shows creating another object, setting some properties on that object, and then using `merge` to put those properties into the server binder.

```
// create an empty content item
ISCSContent content = (ISCSContent)getUCPMAPI ().createObject (ISCSContent.class);

// set some properties
content.setTitle ("test");
content.setSecurityGroup ("Public");

// merge into binder; this copies all the properties from content into the binder
binder.mergeObject (content);
```

The above two examples are identical: they both result in the setting of `dDocTitle` and `dSecurityGroup` native properties in the `ISCSServerBinder` object. However, by using the second method, we abstract ourselves from having to deal with the specifics of content server naming. The `ISCSContent` object handles the mapping of standard Java properties into content server metadata.

Result Sets

A result set represents a collection of rows returned from a content server query. This is exposed in `ISCSServerBinder` via the `getResultSet` and `setResultSet` methods. A result set in the SCS API is then exposed as a homogeneous `List`, containing a type of object that represents a single row of the result set. Many items returned from content server queries come back as result sets. As all the result sets are lists of `ISCSObject` objects, the items from the result sets can be used in other calls. For example, look at the following code snippet where a search is executed and the first item then has its contents updated:

```
// create a simple query
ISCSSearchQuery query =
    (ISCSSearchQuery)getUCPMAPI ().createObject (ISCSSearchQuery.class):
    query.setQueryText ("dDocName <substring> 'test' ");

// execute a search
ISCSSearchResponse response =
    getUCPMAPI ().getActiveAPI ().getSearchAPI ().search (context, query);

// search results come back as a result set of ISCSSearchResult items
ISCSSearchResult result = (ISCSSearchResult)response.getResults ().get (0);

// change the title and check it in
result.setTitle ("new title");
getUCPMAPI ().getActiveAPI ().getDocumentUpdateAPI ().
    updateInfo (context, result);
```

File Objects

The `ISCSServerBinder` allows for the sending of files to the content server via the `addFile` method. This method takes an `ICISTransferStream`. The resulting file is sent to the content server, along with the binder, during the request. Adding a file is similar to adding a property:

```
// create an empty stream
ICISTransferStream stream = getUCPMAPI ().createTransferStream ();

// point the stream at a local file
stream.setFile (new File ("testfile.txt"));

// add the stream to the binder
serverBinder.addStream ("myFile", stream);
```

When the above binder is sent to the content server, the stream will be transferred along with the binder. Inside the content server, the stream will be available under the key "myFile" that was specified when adding the stream to the binder.

Object Copying and Casting

Each ISCSObject in the SCS API has an object that holds the data in a low-level format compatible with content server. This object, referred to as a Data Object, is used by all ISCSObject implementations. This implies that any ISCSObject can be mutated to any other type of ISCSObject. There are two methods that expose this functionality: the `castObject` and `copyObject` methods available on the ISCSObject interface.

Both methods take in a single parameter: a class type representing the type of object that should be created. A call to `castObject` will result in the creation of a new object that points at the same backing data of the object it was invoked against. This implies that changes to the original object will be reflected in the object returned from the `castObject` call as well. A call to `copyObject` will result in a copy of the backing data being made, allowing the newly created object to act independently from the original object.

For example, imagine there is a custom content server service called "MY_DOC_INFO" which is similar to the standard "DOC_INFO" but it does some extra business logic processing. However, the returned binder from the "MY_DOC_INFO" call is very close to the "DOC_INFO" call. Since there is no explicit API call in the SCS API to call this "MY_DOC_INFO" service, we have to use the generic `executeIDCService` call. But we can use the `castObject` method to change the return type into something more user friendly:

```
// build our custom call
ISCSServerBinder binder =
    (ISCSServerBinder)getUCPMAPI ().createObject (ISCSServerBinder.class);
    binder.setService ("MY_DOC_INFO");

// create a document ID and add it to the binder
ISCSDocumentID documentID =
    (ISCSDocumentID)getUCPMAPI ().createObject (ISCSDocumentID.class);
    documentID.setDocumentID ("12345");
    binder.mergeObject (documentID);

// execute the call
ISCSServerResponse response =
    (ISCSServerResponse)getUCPMAPI ().getAdministrativeAPI ().
        executeIDCService (context, binder);

// use the cast to change it to a ISCSDocumentInformationResponse
ISCSDocumentInformationResponse infoResponse =
    (ISCSDocumentInformationResponse)response.
        castObject (ISCSDocumentInformationResponse.class);

// use the info response as usual
System.out.println ("Title: " + infoResponse.getDocNode ().getTitle ());
```

As mentioned above, the `castObject` call links the two objects by sharing the same backing data. In the above example, any changes made to the response object would be reflected in the `infoResponse` object as well:

```
// set a property on the response
response.setProperty ("customProperty", "customValue");

// value is then available in the infoResponse object
String value = infoResponse.getPropertyAsString ("customProperty");
```

If `copyObject` was called instead, the response and `infoResponse` would be independent of each other. The `castObject` creates a smaller memory footprint than `copyObject` as the result from a `castObject` call does not create a new backing data object.

3.2.4 Interface `ISCSServerResponse`

The result of a call to the SCS API is usually an `ISCSServerResponse` object. The `ISCSServerResponse` is the base interface for all the response objects. It encapsulates the response from the content server for the last request. Most methods have specific implementations of this interface, which provide properties that are specific to those responses. See the JavaDocs for the specific response objects, and the properties available to each.

In the current release, some calls that previously returned references to an `InputStream` now return a `ICISTransferStream` object instead. See the next section, Interface `ICISTransferStream` on how to use the new transfer stream interface.

3.2.5 Interface `ISCSRequestModifier`

All requests to the content server via the SCS API result in the creation of an `ISCSServerBinder` object. In certain situations, it becomes necessary to change the binder contents for a given API call to match the requirements of a specific content server. The `ISCSRequestModifier` interface is designed for this very purpose: to augment a call to the content server with custom modifications.

All APIs in the SCS API have a corresponding method that takes as the first parameter an `ISCSRequestModifier` object. Look at the API for `ISCSSearchAPI`:

```
/**
 * Command the implements searching against the content server.
 * @param SCSContext the context object representing the current user
 * @param searchQuery the content server query object
 */

public com.stellent.cis.client.api.scs.search.
  ISCSearchResponse search (com.stellent.cis.client.api.scs.context.
    ISCSContext SCSContext,

com.stellent.cis.client.api.scs.search.ISCSearchQuery searchQuery)
  throws com.stellent.cis.client.command.CommandException;

/**
 * Command the implements searching against the content server.
 * @param requestModifier modify the request
 * @param SCSContext the context object representing the current user
 * @param searchQuery the content server query object
 * @see com.stellent.cis.server.api.scs.commands.search.SearchCommand
 */
```

```

public com.stellent.cis.client.api.scs.search.
    ISCSSearchResponse search (com.stellent.cis.client.api.scs.
        ISCSRequestModifier requestModifier, com.stellent.cis.client.api.scs.context.
        ISCSContext SCSCContext, com.stellent.cis.client.api.scs.search.I
        SCSSearchQuery searchQuery)
    throws com.stellent.cis.client.command.CommandException;

```

The second API takes the all the parameters as the first with the additional `ISCSRequestModifier` argument. The standard Search API, and all its logic, can be used and custom logic added. For example, imagine a custom component installed on the content server that will do some extra processing if it find the "myCustomProperty" property set during a search query. To do this with CIS, we can use the `ISCSRequestModifier` to change the binder as follows:

```

// build a search query
ISCSSearchQuery query =
    (ISCSSearchQuery)getUCPMAPI ().createObject (ISCSSearchQuery.class);
query.setQueryText ("dDocName <substring> `test`");

// build a request modifier
ISCSRequestModifier modifier =
    (ISCSRequestModifier)getUCPMAPI ().createObject (ISCSRequestModifier.class);

// access the binder off the modifier and add in our custom data
modifier.getServerBinder().setProperty ("myCustomProperty", "customValue");

// execute the search as normal
getUCPMAPI ().getActiveAPI ().getSearchAPI ().search (modifier, context, query);

```

Now the binder we modified will be used during the search call. Our custom property value will get sent along with the standard search call. This same method can be used to set any properties, add files, set result sets or even override which service call is being made on the content server.

3.3 Understanding the SCS API Servlets

The SCS API requires that a number of servlets be available to the system while operating in a J2EE/Web environment and running in server mode.

This section contains the following topics:

- ["Servlet Descriptions"](#) on page 3-8
- ["SCS Servlet Parameters"](#) on page 3-9
- ["Servlet Security"](#) on page 3-10
- ["Servlets and API Interaction"](#) on page 3-11

3.3.1 Servlet Descriptions

This table lists the servlet names and the appropriate configuration information needed in the `web.xml` file for a given web application:

Fully Qualified Name	Mapping	Description
SCSFileDownloadServlet com.stellent.web.servlets.SCSFileDownloadServlet	/getfile	Allows clients to retrieve files from the content server.

Fully Qualified Name	Mapping	Description
SCSCommandClientServlet com.stellent.web.servlets.SCSCommandClientServlet	/scscommandclient	Publishes the CIS server configuration information for CIS clients.
SCSFileTransferServlet com.stellent.web.servlets.SCSFileTransferServlet	/scsfiletransfer	Allows UCPM APIs to transfer files to a CIS client.
SCSInitialize com.stellent.web.servlets.SCSInitialize	N/A	Initializes the CIS Application instance. Should be set as a LoadOnStartup servlet.
SCSDynamicConverterServlet com.stellent.web.servlets.SCSDynamicConverterServlet	/getdynamicconversion/*	Executes a dynamic conversion and streams the result to the client.
SCSDynamicURLServlet com.stellent.web.servlets.SCSDynamicURLServlet	/scsdynamic/*	Retrieves dynamic files from the content server; used when rewriting the dynamically converted document URLs.

3.3.2 SCS Servlet Parameters

This section provides a description of the parameters for these servlets:

- ["SCSFileDownloadServlet"](#) on page 3-9
- ["SCSDynamicConverterServlet"](#) on page 3-10
- ["SCSDynamicURLServlet"](#) on page 3-10

This section does not specify any of the available security parameters, which are detailed in ["Servlet Security"](#) on page 3-10. All calls made to the content server use the identity as specified in the servlet security section.

3.3.2.1 SCSFileDownloadServlet

Property	Required	Description
adapterName	true	The adapter name to query for the document.
dDocName	n/a	The content ID of the document to retrieve.
rendition	false	The content rendition; valid only when specifying the dDocName.
revisionSelection	false	The revisionSelection to use when selecting content; valid only when specifying the dDocName.
forceStream	false	If true, the contents are streamed from the content server via the GET_FILE call regardless of optimized file transfer settings for the adapter; defaults to false.

3.3.2.2 SCSDynamicConverterServlet

Property	Required	Description
adapterName	true	The adapter name to query for the document.
contentID	Either contentID or documentID is required.	The content ID (dDocName) of the document to retrieve.
documentID	n/a	The documentID (dID) of the document to retrieve.
rendition	false	The rendition of the document to retrieve; valid only if contentID is specified.
revisionSelectionMethod	false	The revisionSelectionMethod to use to select the document; valid only if contentID is specified.
viewFormat	false	The viewFormat of the conversion (i.e. Native or WebViewable).
useAlternate	false	If true, use the alternate file for conversion; default is false.

3.3.2.3 SCSDynamicURLServlet

Property	Required	Description
adapterName	true	The adapter name to query for the document; not passed in as a parameter, but, rather, specified as the last segment on the URL: /cis-server/scsdynamic/ <adaptername>?...
fileUrl	true	The relative path to the content server file to retrieve.

3.3.3 Servlet Security

All servlets, except for SISFileDownloadServlet and SCSInitializeServlet, make UCPM API calls and therefore must have a user context. By default, they will use the `HttpServletRequest.getUserPrincipal()` method to determine the user ID and pass that ID via the `ISCSContext` object to the UCPM API call. This behavior can be overridden by specifying a couple of initialization parameters to the servlet:

- **principalLookupAllowed:** If set to `TRUE`, the servlet will look for a user ID in the configured scope. Default scope is *session*.
- **principalLookupScope:** The scope of the lookup. Valid if `principalLookupAllowed` is `TRUE`. The defined scope will be used to call the `getAttribute ()` method to discover the name of the current user; can be either *request*, *session*, or *application*. Default is *session*.
- **principalLookupName:** The name of the scoped parameter that holds the user ID. Valid if `principalLookupAllowed` is `TRUE`. Default is *principal*.
- **getUserPrincipalEnabled:** If set to `FALSE`, no call will be made to the `HttpServletRequest.getUserPrincipal ()` method to determine the user ID. Default is `TRUE`.

- **principal:** The default user ID if no user ID can be determined. Default is *guest*.

To determine the current user ID, the servlets will first check the status of the `principalLookupAllowed` flag. If `TRUE`, it looks up the name of the user by determining the scope as set by the parameter `principalLookupScope`. With the current scope, the `getAttribute ()` method is called, using `principalLookupName` as the parameter. If it is unable to locate a principal, it then checks the status of the `getUserPrincipalEnabled` flag. If that flag is `TRUE`, it calls the `HttpServletRequest.getUserPrincipal ()` method. If that returns null, it uses the default principal to execute the request.

Without any changes to the servlet, the default behavior is to check the `HttpServletRequest.getUserPrincipal ()` method and then use the default, if necessary. The other checks on the request, session, and application are done only if specified in the **init-param** of the servlet definition in the `web.xml` file.

3.3.4 Servlets and API Interaction

The `ISCSFileAPI.getDynamicConversion()` method performs a dynamic conversion of the given document (assuming the Dynamic Converter component is installed on the content server). The `getDynamicConversion()` call will also rewrite the returned URLs, so that they point back to the CIS servlets (as opposed to pointing directly to the content server) and display properly in the Web/Portal environment when they are rendered.

The rewritten URLs point back to `SCSDynamicURLServlet`, which then retrieves the item from the content server, via the SCS API, and streams it back to the client. The servlet determines the user ID for the context by the method described in "[Servlet Security](#)" on page 3-10.

Since the servlet determines the user ID, the user who executed the `getDynamicConversion()` call might not have the same user ID as the user clicking a link on the rendered HTML. This would be the case if the `HttpServletRequest.getUserPrincipal()` user ID does not match the `ISCSContext` user ID

In that event, the `SCSDynamicURLServlet` can be directed to look for a user parameter on the session by customizing it via the methods described under "[Servlet Security](#)" on page 3-10. Alternatively, `SCSDynamicURLServlet` can call the `getDynamicConversion()` and pass in an `ISCSConvertedUrlInfo` object that allows a user to optionally add parameters to the URL, which can then be used by your application to identify the context.

For example, if your application stored the current User ID in a session attribute named `stellentPrincipal`, you would modify the `web.xml` for the `SCSDynamicURLServlet` (and other servlets, as necessary) as follows:

```
<servlet>
  <servlet-name>scsdynamic</servlet-name>
  <servlet-class>com.stellent.web.servlets.SCSDynamicURLServlet</servlet-class>
  <init-param>
    <param-name>sessionPrincipalAllowed</param-name>
    <param-value>true</param-value>
  </init-param>
  <init-param>
    <param-name>sessionPrincipalName</param-name>
    <param-value>stellentPrincipal</param-value>
  </init-param>
</servlet>
```

3.4 Using the SCS APIs

The SCS Search, SCS File, SCS Document, and SCS Workflow APIs are discussed and sample code provided. These APIs perform task such as searching, checking in and out of content, and workflow approval and rejection.

It is assumed that you have initialized a CISApplication instance (referred to as `m_cisApplication`) and created a context object (referred to as `m_context`). Additional samples can be found in the `SDK/Samples/CodeSamples/` directory.

This section contains the following topics:

- ["SCS Search API"](#) on page 3-12
- ["SCS File API"](#) on page 3-12
- ["SCS Document APIs"](#) on page 3-13
- ["SCS Workflow API"](#) on page 3-14

3.4.1 SCS Search API

The `ISCSSearchAPI` is the command API implementation of the search commands. You can use `ISCSSearchAPI` to search the content server using the following code:

```
// get a handle to the SCS Search API
ISCSSearchAPI searchAPI =
    m_cisApplication.getUCPMAPI ().getActiveAPI ().getSearchAPI ();
ISCSSearchResponse searchResponse =
    searchAPI.search (m_context, "dDocTitle <substring> 'HR'", 25);

// iterate all results
for (Iterator it = searchResponse.getResults ().iterator (); it.hasNext (); ) {
    ISCSSearchResult searchResult = (ISCSSearchResult)it.next ();

// print out the title and author
System.out.println ("Found result: " + searchResult.getTitle () + " by " +
    searchResult.getAuthor ());
}
```

3.4.2 SCS File API

The `ISCSFileAPI` deals with the retrieval of files, and the dynamic conversions of files, from the content server. A file can be retrieved simply by passing in the ID for the content. Alternatively, different versions of the file can be retrieved by using the optional `ISCSFileInfo` object to obtain references to the Web and Alternate versions of the file.

```
// get the SCS File API
ISCSFileAPI fileAPI =
    m_cisApplication.getUCPMAPI ().getActiveAPI ().getFileAPI ();

ICISTransferStream transferStream =
    fileAPI.getFile (m_context, content.getDocumentID ());

InputStream stream = transferStream.getInputStream();
// do something with the stream...
```

You can also use the `_createFileInfo()` method to get an `ISCSFileInfo` object. This object has several properties, which allow one to further select which rendition of a file to retrieve. The following sample uses the `fileinfo` object to get the Web Viewable rendition of a file. A similar process can be used to get the Alternate rendition.

```
// get the web viewable version of the file
ISCSFileInfo fileInfo =
    (ISCSFileInfo) m_cisApplication.getUCPMAPI ().createObject(ISCSFileInfo.class);
fileInfo.setRendition ("Web");

// get the file
ICISTransferStream transferStream =
    fileAPI.getFile (m_context, content.getDocumentID (), fileInfo);
    InputStream stream = transferStream.getInputStream();
// do something with the stream...
```

The SCS File API can be used to generate HTML renditions of the content via the Dynamic Converter component of the content server (you must have the Dynamic Converter component installed).

In a similar fashion to the `getFile ()` calls, you can either call `getDynamicConversion ()` with an ID to retrieve the HTML conversion, or you can use the `ISCSFileInfo` and `ISCSConvertedFileInfo` objects to pass information into the API to process conversion rules and apply explicit templates.

```
ICISTransferStream transferStream =
    fileAPI.getDynamicConversion (m_context, content.getDocumentID ());
// process the stream...
```

The following sample combines the above features in one method that dynamically converts the alternate rendition of a given content object by using a custom conversion template.

```
// create the converted file bean and set our properties
ISCSConvertedFileInfo convertedInfo = fileAPI.__createConvertedFileInfo ();
convertedInfo.setConversionLayout ("custom_layout");
convertedInfo.setRendition ("Alternate");

// execute the dynamic conversion
ICISTransferStream transferStream =
    fileAPI.getDynamicConversion (m_context, content.getDocumentID (),
    convertedInfo);
// do something with the stream...
```

3.4.3 SCS Document APIs

The SCS Document APIs deal with content in the content server, including the checking in and out of content, content information, and the deletion of content.

This section provides a description of these APIs:

- ["ISCSDocumentCheckinAPI"](#) on page 3-13
- ["ISCSDocumentCheckoutAPI"](#) on page 3-14

3.4.3.1 ISCSDocumentCheckinAPI

This API deals with the check-in of all content to the content server. For a simple check-in of a file from disk, the following code will work:

```
// get the checkin api
ISCSDocumentCheckinAPI checkinAPI =
    m_cisApplication.getUCPMAPI ().getActiveAPI ().getDocumentCheckinAPI ();

// create an empty content object with the specified content ID
ISCSContent content =
    (ISCSContent) m_cisApplication.getUCPMAPI ().createObject(ISCSContent.class);
```

```

ISCSContentID contentID =
(ISCSContentID) m_cisApplication.getUCPMAPI ().createObject (ISCSContentID.class);
contentID.setContentID ("my_test_file");
content.setContentID (contentID);
content.setAuthor (m_context.getUser ());
content.setTitle ("Custom Title");
content.setSecurityGroup ("Public");
content.setType ("ADACCT");

// get the file stream
File myFile = new File ("c:/test/testcheckin.txt");
ICISTransferStream transferStream =
    m_cisApplication.getUCPMAPI ().createTransferStream();
transferStream.setFile (myFile);

// execute the checkin
checkinAPI.checkinFileStream (m_context, content, transferStream);

```

In many deployments of the content server, there are required extended properties that need to be set for a new piece of content. These properties can be set on the content object via the `setProperty()` call available to all `ICISObject` objects. For example, some custom properties can be set as follows:

```

//set an extended property
content.setProperty ("xCustomProperty", "Custom Value");

```

You can use the `setProperty()` method to set all the properties as opposed to calling the **setter** methods. You can use either the JavaBean name (for example, *title*) or the native content server property name that the JavaBean property corresponds to (that is, *dDocTitle*). In the next sample, we will set the title property in three ways, all equivalent:

```

// set via a standard property setter
content.setTitle ("My Title");

// set a standard property using the JavaBean property name
content.setProperty ("title", "My Title");

// set a property using the native content server property name
content.setProperty ("dDocTitle", "My Title");

```

3.4.3.2 ISCSDocumentCheckoutAPI

This API deals with checking out content from the content server. Content items are identified by their ID.

```

// get the checkout api
ISCSDocumentCheckoutAPI checkoutAPI =
    m_cisApplication.getUCPMAPI ().getActiveAPI ().getDocumentCheckoutAPI ();

// checkout the file
checkoutAPI.checkout (m_context, content.getDocumentID ());

```

3.4.4 SCS Workflow API

The `ISCSWorkflowAPI` deals with the workflow commands such as approval and rejection, viewing a user's workflow queue, and interacting with the content server workflow engine. The following sample code shows an example of querying the workflow engine for the workflows currently active in the system:

```

// get the workflow API
ISCSWorkflowAPI workflowAPI =
    m_cisApplication.getUCPMAPI ().getActiveAPI().getWorkflowAPI ();
ISCSWorkflowResponse workflowResponse =
    workflowAPI.getActiveWorkflows (m_context);

// iterate through the workflows
for (Iterator it = workflowResponse.getActiveWorkflows().iterator();
     it.hasNext (); ) {
    ISCSWorkflow workflow = (ISCSWorkflow)it.next ();
    String name = workflow.getName ();
    String status = workflow.getWorkflowStatus ();
    System.out.println ("SCS workflow: " + name + "; status = " + status);
}

```

The most common interaction with workflows is to reject them or approve them and advance them to the next step in the workflow. The following code illustrates how to get a user's personal workflow queue and approve all workflows pending:

```

// get the workflow API
ISCSWorkflowAPI workflowAPI =
    m_cisApplication.getUCPMAPI ().getActiveAPI().getWorkflowAPI ();

// get the workflow queue
ISCSWorkflowQueueResponse queueResponse =
    workflowAPI.getWorkflowQueueForUser (m_context);
for (Iterator it = queueResponse.getWorkflowInQueue().iterator(); it.hasNext();) {
ISCSWorkflowQueueItem queueItem =
    (ISCSWorkflowQueueItem)it.next();

// approve the workflow
workflowAPI.approveWorkflow(m_context, queueItem.getDocumentID ());
}

```


A

accessor methods, 2-9
Adapter element, 2-11
API object
 ISCObject, 3-2
 ISCServerResponse, 3-2
API objects, calling, 2-7

C

character encoding, 1-2
CIS API
 calling methods, 2-2
 command objects, 1-1
 ICISCommonContext bean, 2-2
 IContext bean, 2-2
 object metadata, 1-1
 object model, 1-1
class
 com.stellent.web.servlets.SCSCommandClientServlet, 3-9
 com.stellent.web.servlets.SCSDynamicConverterServlet, 3-9
 com.stellent.web.servlets.SCSDynamicURLServlet, 3-9
 com.stellent.web.servlets.SCSFileDownloadServlet, 3-8
 com.stellent.web.servlets.SCSFileTransferServlet, 3-9
 com.stellent.web.servlets.SCSInitialize, 3-9
Command Design Pattern, 1-1
config element, 2-11
Content Integration Suite
 layered architecture, 1-1

D

DocumentCheckin, 3-13
DocumentCheckout, 3-14

G

getProperty() method, 2-10, 3-2
getUCPMAPI () method, 2-1, 3-1
getUserPrincipalEnabled, 3-10
getValue() method, 2-10

I

ICISCommonContext, 2-8
ICISCommonContext bean, 2-2
ICISObject, 2-7, 2-9
 property methods, 2-9
ICISObjects, 2-2
IContext, 2-8
IContext bean, 2-2
initialization parameter
 getUserPrincipalEnabled, 3-10
 principal, 3-11
 principalLookupAllowed, 3-10
 principalLookupName, 3-10
 principalLookupScope, 3-10
internationalization (character encoding), 1-2
ISCFileAPI, 3-12
ISCObject object, 3-2
ISCSearchAPI, 3-12
ISCServerResponse, 3-2
ISCWorkflowAPI, 3-14

J

J2EE
 Command Design Pattern, 1-1
 compliant application server, 1-1
Java Virtual Machine. See JVM
JVM
 application, 1-1

O

Objects, 2-8, 2-9

P

principal, 3-11
principalLookupAllowed, 3-10
principalLookupName, 3-10
principalLookupScope, 3-10
property accessors, 2-9
property collections, 2-10
property object type, 2-10
PropertyRetrievalException, 2-9

S

SCS API

- date format, 3-3
- DocumentCheckin, 3-13
- DocumentCheckout, 3-14
- explained, 3-1
- interaction with servlets, 3-11
- ISCSFileAPI, 3-12
- ISCSSearchAPI, 3-12
- ISCSWorkflowAPI, 3-14
- Servlet security, 3-10
- Servlets and API interaction, 3-11
- setProperty () method, 2-10

U

UCPM API

- calls, 2-7
- explained, 1-1, 2-1, 3-1
- ICISObject, 2-7
- methodology, 2-2
- SCS API, 3-1
- UTC time, 3-3

V

- value objects, 2-9