

Oracle® Retail Store Inventory Management
Implementation Guide, Volume 4 – Extension Solutions
Release 13.2.5

October 2012

Oracle Retail Store Inventory Management Implementation Guide, Volume 4 – Extension Solutions, Release 13.2.5

Copyright © 2012, Oracle and/or its affiliates. All rights reserved.

Primary Author: Graham Fredrickson

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Value-Added Reseller (VAR) Language

Oracle Retail VAR Applications

The following restrictions and provisions only apply to the programs referred to in this section and licensed to you. You acknowledge that the programs may contain third party software (VAR applications) licensed to Oracle. Depending upon your product and its version number, the VAR applications may include:

(i) the **MicroStrategy** Components developed and licensed by MicroStrategy Services Corporation (MicroStrategy) of McLean, Virginia to Oracle and imbedded in the MicroStrategy for Oracle Retail Data Warehouse and MicroStrategy for Oracle Retail Planning & Optimization applications.

(ii) the **Wavelink** component developed and licensed by Wavelink Corporation (Wavelink) of Kirkland, Washington, to Oracle and imbedded in Oracle Retail Mobile Store Inventory Management.

(iii) the software component known as **Access Via**™ licensed by Access Via of Seattle, Washington, and imbedded in Oracle Retail Signs and Oracle Retail Labels and Tags.

(iv) the software component known as **Adobe Flex**™ licensed by Adobe Systems Incorporated of San Jose, California, and imbedded in Oracle Retail Promotion Planning & Optimization application.

You acknowledge and confirm that Oracle grants you use of only the object code of the VAR Applications. Oracle will not deliver source code to the VAR Applications to you. Notwithstanding any other term or condition of the agreement and this ordering document, you shall not cause or permit alteration of any VAR Applications. For purposes of this section, "alteration" refers to all alterations, translations, upgrades, enhancements, customizations or modifications of all or any portion of the VAR Applications including all reconfigurations, reassembly or reverse assembly, re-engineering or reverse engineering and recompilations or reverse compilations of the VAR Applications or any derivatives of the VAR Applications. You acknowledge that it shall be a breach of the agreement to utilize the relationship, and/or confidential information of the VAR Applications for purposes of competitive discovery.

The VAR Applications contain trade secrets of Oracle and Oracle's licensors and Customer shall not attempt, cause, or permit the alteration, decompilation, reverse engineering, disassembly or other reduction of the VAR Applications to a human perceivable form. Oracle reserves the right to replace, with functional equivalent software, any of the VAR Applications in future releases of the applicable program.

Contents

Send Us Your Comments	xvi
Preface	xviii
Audience.....	xviii
Documentation Accessibility	xviii
Related Documents	xix
Customer Support	xix
Review Patch Documentation	xix
Oracle Retail Documentation on the Oracle Technology Network	xix
Conventions	xx
1 Customization	
Build/Packaging/Deployment Related	1-1
Architecture	1-1
Process Overview	1-1
Adding Attribute to Pre-Existing Data & Workflows	1-2
Add the New Attribute to the Database	1-2
Database Tables.....	1-2
Create New Attribute Column.....	1-2
Update DAO (Database Access Objects)	1-2
Create DAO Code to Access Information	1-2
Performing Simple Insert.....	1-3
Performing Simple Query.....	1-3
Creating a Data Bean	1-3
Update Business Object or Value Object	1-4
Update the Services.....	1-4
Service Index.....	1-5
Update the PC Screen	1-6
Update the HH Forms	1-7
Adding New Workflows	1-8
Example Code.....	1-8
Building Business Objects	1-9
The Business Object Class.....	1-9
Query Filter	1-10

Value Object.....	1-10
Customization Using the Rules Engine	1-10
Creating a New Business Rule	1-11
Building Enterprise Java Bean (EJB) Services	1-12
Building Data Access	1-13
Database Layer Development Tips	1-13
Creating a DAO.....	1-14
DAO Methods	1-14
Building PC Screens.....	1-15
Customization Guidelines for the PC	1-15
PC Client Architecture	1-15
Navigation.....	1-16
External Configurable Navigation	1-16
Hard-Coded Navigation.....	1-16
Screens	1-16
Features of the Screen.....	1-18
Screen Panels	1-19
Editors.....	1-20
Initializing Editors	1-20
Editor Layout.....	1-21
Search Editor.....	1-21
Using a Search Editor	1-21
SimTable	1-23
Using a SimTable	1-23
SimTableDefinition.....	1-24
SimTableAttribute	1-24
Displayers	1-25
Creating a New Displayer	1-25
The Displayable Interface	1-26
TableEditors.....	1-26
Triggering User Interface Events.....	1-28
Screen Models.....	1-30
Features of the Model.....	1-31
Dialog Windows	1-31
Error & Message Dialogs	1-31
Confirmation	1-32
Pop-up Windows	1-32
Building Wireless Forms	1-32
Wireless Application Architecture	1-33
Wireless Framework.....	1-33
Form_<name>	1-33
EventHandler_<name>.....	1-33
<functional area>Utility	1-33
EJB Service	1-33
Forms	1-33
Event Handler	1-33
SimEventHandler.....	1-35

YesNoEventHandler.....	1-35
Wireless Context	1-36
Wireless Utilities	1-37
Form Paging.....	1-38
Customizing Wireless Forms	1-39
Coding Guidelines	1-39
Creating a New Context.....	1-40
Creating a New Utility	1-40
Altering Code in an EventHandler	1-40
Altering Code in a Form	1-40
Significant Classes to Understand	1-41
Exceptions and Logging	1-41
Exceptions	1-41
Exception Handling	1-42
The DAO Layer	1-42
The Service Layer	1-42
The UI Layer	1-43
Throwing an Exception.....	1-43
Catching an Exception.....	1-43
Processing an Exception.....	1-44
Logging	1-45
LogService	1-45
Debugging.....	1-46
Logs	1-47
Client Side Logs.....	1-47
Server Side Logs	1-47
Exception Format	1-47
Modifying Data Transport to External Systems	1-48
Process of Receiving an External Message	1-48
Process of Sending an External Message	1-48
Update DEOs	1-49
Update Injectors	1-49
Update Consumers	1-50
Update Stagers.....	1-51
Update Publishers	1-51
Modifying Source Code	1-51
Customizing Look and Feel	1-52
Customizing Barcodes	1-52
Creating a Barcode Processor	1-53
Customizing E-mail Alerts	1-54
The E-mail Server Configuration.....	1-54
E-mail Server Class Definitions.....	1-55
SIM E-mail System Configuration Values.....	1-55
SIM E-mail Batch Jobs.....	1-56
SIM-Developed Classes Involved.....	1-56
Customizing an E-mail.....	1-57

2 SIM Standalone Integration

Customizations	2-1
Creating a Custom Consumer	2-1
Creating a Custom Stager	2-2

3 Customizing Internationalization

Customizing a Language	3-1
Insert a Record into RK_TRANSLATION_LOCALE	3-1
Create an RK_TRANSLATION_DETAIL Row.....	3-2
Create a Translation.....	3-2
Assign a Correct Locale to a User	3-2

A Appendix: Web Services

Asynchronous Operations	A-2
Application Programming Interface (API)	A-2
Implementation	A-3
Security	A-3
Deployment	A-3
Definition Files and Services	A-3
Web Service APIs	A-5
lookupItem	A-5
lookupItemDetail	A-7
lookupItemMarkdowns	A-10
lookupReturnHeader.....	A-12
lookupReturnDetail	A-14
updateReturn	A-16
lookupTransferHeader	A-17
lookupTransferDetail.....	A-20
updateTransfer	A-22
processItemImage	A-24
Web Services	A-25
Lookup Return Detail	A-25
SIM Inbound Information.....	A-25
SIM Outbound Information.....	A-25
Fail Messages	A-25
Web Service Input.....	A-25
Web Service Output.....	A-25
Web Service Error Messages	A-26
Lookup Return Header	A-27
SIM Inbound Information.....	A-27
SIM Outbound Information.....	A-27
Fail Messages	A-27
Web Service Input.....	A-27
Web Service Output.....	A-28
Web Service Error Messages	A-29
Item Lookup.....	A-29

SIM Inbound Information.....	A-29
SIM Outbound Information.....	A-29
Fail Messages	A-29
Web Service Input.....	A-29
Web Service Output.....	A-30
Web Service Error Messages	A-31
Item Detail Lookup	A-31
SIM Inbound Information.....	A-31
SIM Outbound Information.....	A-31
Fail Messages	A-31
Web Service Input.....	A-32
Web Service Output.....	A-32
Web Service Error Messages	A-34
Update Return	A-34
SIM Inbound Information.....	A-34
SIM Outbound Information.....	A-34
Fail Messages	A-34
Web Service Input.....	A-35
Web Service Output.....	A-35
Web Service Error Messages	A-36
Lookup Transfer Header.....	A-36
SIM Inbound Information.....	A-36
SIM Outbound Information.....	A-36
Fail Messages	A-37
Web Service Input.....	A-37
Web Service Output.....	A-38
Web Service Error Messages	A-38
Lookup Transfer Detail	A-39
SIM Inbound Information.....	A-39
SIM Outbound Information.....	A-39
Fail Messages	A-39
Web Service Input.....	A-39
Web Service Output.....	A-40
Web Service Error messages.....	A-41
Update Transfer.....	A-41
SIM Inbound Information.....	A-41
SIM Outbound Information.....	A-41
Fail Messages	A-41
Web Service Input.....	A-42
Web Service Output.....	A-42
Web Service Error Messages	A-42
Lookup Markdowns	A-43
SIM Inbound Information.....	A-43
SIM Outbound Information.....	A-43
Fail Messages	A-44
Web Service Input.....	A-44
Web Service Output.....	A-45

Web Service Error Messages A-45

Process Item Image A-46

 SIM Inbound Information..... A-46

 SIM Outbound Information..... A-46

 Fail Messages A-46

 Web Service Input..... A-46

 Web Service Output..... A-46

 Web Service Error messages..... A-47

B Appendix: Code Examples

List of Examples

1-1	common.cfg.....	1-5
1-2	Overriding the Execute() Method.....	1-11
1-3	Implementing the Typed Execute() Method.....	1-11
1-4	rules_sim.xml	1-11
1-5	InventoryAdjustmentFilterDialog.....	1-20
1-6	CustomUINCreatePanel	1-23
1-7	CustomUINCreatePanel	1-23
1-8	ItemLookupPanel.....	1-23
1-9	ItemLookupPanel.....	1-23
1-10	CustomUINCreatePanel	1-23
1-11	StoreDisplayer	1-25
1-12	StoreDisplayer	1-26
1-13	DirectDeliveryDetailPanel.....	1-27
1-14	DirectDeliveryDetailPanel.....	1-27
1-15	CustomUINCreateWrapper	1-27
1-16	ItemVO	1-28
1-17	DirectDeliveryCreatePanel	1-29
1-18	DirectDeliveryCreatePanel	1-29
1-19	ReturnDetailPanel.....	1-30
1-20	ItemTicketListPanel	1-31
1-21	ReturnDetailPanel.....	1-32
1-22	MacroSequenceListPanel	1-32
1-23	Screen_InventoryAdjustmentNormalItem.....	1-33
1-24	AbstractEventHandler_InventoryAdjustmentNormalItem	1-34
1-25	RequestCancelYesNoHandler.....	1-35
1-26	InventoryAdjustmentContext	1-36
1-27	InventoryAdjustmentWirelessUtility	1-37
1-28	InventoryAdjustmentWirelessUtility	1-37
1-29	PageableEventInterface.....	1-38
1-30	EventHandler_ItemRequestSelectRequest	1-38
1-31	EventHandler_ItemRequestSelectRequest	1-38
1-32	EventHandler_ItemRequestSelectRequest	1-39
1-33	EventHandler_ItemRequestSelectRequest	1-39
1-34	MyCustomUtility	1-40
1-35	ProductGroupDao	1-42
1-36	ProductGroupOracleDao.....	1-42
1-37	ReplenishmentServerServices	1-43
1-38	PickListUpdateCommand	1-43
1-39	ItemTicketListModel	1-43
1-40	ItemTicketListScreen	1-44
1-41	ItemTicketListPanel	1-44
1-42	SimStore.....	1-46
1-43	EmailDispatcher	1-46
1-44	ReturnCreateLineItemRule.....	1-46
B-1	CustomSerialNumber.....	B-1
B-2	CustomUINBean	B-2
B-3	CustomUINCountTableEditor	B-3
B-4	CustomUINCreateDialog	B-6
B-5	CustomUINCreateDialogModel.....	B-11
B-6	CustomUINCreateDialogTableEditor	B-12
B-7	CustomUINCreateModel.....	B-17
B-8	CustomUINCreatePanel	B-18
B-9	CustomUINCreateScreen.....	B-22
B-10	CustomUINCreateWrapper	B-23

B-11	CustomUINDataBean.....	B-24
B-12	CustomUINEJBServices	B-27
B-13	CustomUINInterface	B-28
B-14	CustomUINOracleDAO.....	B-28
B-15	CustomUINServerServices	B-29
B-16	CustomUINServices	B-30

List of Figures

1-1	InventoryAdjustmentFilterDialog.....	1-21
1-2	Table Editor Error Screen.....	1-45
1-3	Severe Error Screen.....	1-45
A-1	Web Service Process Flow	A-2

List of Tables

1-1	PC_MENU_ITEM Table.....	1-6
1-2	PC_MENU_ITEM Table, Item Detail.....	1-7
1-3	PC_MENU_ITEM Table, Custom Screen.....	1-7
1-4	Example Code Files.....	1-8
1-5	BusinessObject Features.....	1-9
1-6	DAO Layer Framework Classes.....	1-14
1-7	Features of the Screen.....	1-18
1-8	Editors.....	1-20
1-9	Search Editor Properties.....	1-22
1-10	SimTableDefinition APIs.....	1-24
1-11	Model Features.....	1-31
1-12	BARCODE_PROCESSOR.....	1-52
1-13	BARCODE_PROCESSOR.....	1-53
3-1	RK_TRANSLATION_LOCALE Record.....	3-1
A-1	Web Service Definition Files.....	A-3
A-2	Web Services.....	A-4
A-3	lookupItem.....	A-5
A-4	LookupItemRequest.....	A-5
A-5	LookupItemResponse.....	A-6
A-6	Response Info.....	A-6
A-7	ItemTypeWSType.....	A-6
A-8	LookupItemFault.....	A-6
A-9	ErrorMessageWSType.....	A-6
A-10	lookupItemDetail.....	A-7
A-11	LookupItemDetailRequest.....	A-7
A-12	LookupItemDetailResponse.....	A-7
A-13	LookupItemDetailSupplier.....	A-9
A-14	LookupItemDetailImage.....	A-9
A-15	ItemStatusWSType.....	A-9
A-16	UINWSType.....	A-9
A-17	PriceWSType.....	A-9
A-18	PromotionWSType.....	A-9
A-19	LookupItemFault.....	A-10
A-20	ErrorMessageWSType.....	A-10
A-21	lookupItemMarkdowns.....	A-10
A-22	LookupItemMarkdownRequest.....	A-10
A-23	LookupItemMarkdownResponse.....	A-10
A-24	LookupItemMarkdownResponseInfo.....	A-11
A-25	LookupItemFault.....	A-11
A-26	ErrorMessageWSType.....	A-11
A-27	lookupReturnHeader.....	A-12
A-28	LookupReturnHeaderRequest.....	A-12
A-29	LookupReturnHeaderResponse.....	A-12
A-30	LookupReturnHeaderResponseDetail.....	A-12
A-31	ShipToEntityWSType.....	A-13
A-32	ReturnStatusWSType.....	A-13
A-33	ReturnFault.....	A-13
A-34	ItemProblemWSInfo.....	A-13
A-35	ErrorMessageWSType.....	A-13
A-36	lookupReturnDetail.....	A-14
A-37	LookupReturnDetailRequest.....	A-14
A-38	LookupReturnDetailResponse.....	A-14
A-39	LookupReturnItemDetail.....	A-15

A-40	ReturnFault	A-15
A-41	ErrorMessageWSType.....	A-15
A-42	updateReturn.....	A-16
A-43	UpdateReturnRequest.....	A-16
A-44	UpdateReturnItemRequest.....	A-16
A-45	UpdateReturnResponse	A-16
A-46	ReturnActionWSType	A-16
A-47	ReturnItemActionWSType	A-16
A-48	ReturnFault	A-17
A-49	ItemProblemWSInfo	A-17
A-50	ErrorMessageWSType.....	A-17
A-51	ItemErrorMessageWSType.....	A-17
A-52	lookupTransferHeader.....	A-17
A-53	LookupTransferHeaderRequest	A-17
A-54	LookupTransferHeaderResponse.....	A-18
A-55	LookupTransferHeaderResponseDetail	A-18
A-56	TransferQueryStatusWSType	A-18
A-57	TransferStatusWSType.....	A-19
A-58	TransferFault	A-19
A-59	ItemProblemWSInfo	A-19
A-60	ErrorMessageWSType.....	A-19
A-61	lookupTransferDetail	A-20
A-62	LookupTransferDetailRequest.....	A-20
A-63	LookupTransferDetailResponse	A-20
A-64	LookupTransferItemDetail	A-21
A-65	TransferFault	A-21
A-66	ErrorMessageWSType.....	A-21
A-67	updateTransfer	A-22
A-68	UpdateTransferRequest	A-22
A-69	UpdateTransferItemRequest	A-22
A-70	UpdateTransferResponse.....	A-22
A-71	TransferActionWSType.....	A-22
A-72	TransferItemActionWSType.....	A-23
A-73	TransferFault	A-23
A-74	ItemProblemWSInfo	A-23
A-75	ErrorMessageWSType.....	A-23
A-76	ItemErrorMessageWSType.....	A-23
A-77	processItemImage	A-24
A-78	processLinesItemImageRequest	A-24
A-79	processItemImageResponse	A-24
A-80	ImageWSType	A-24
A-81	ErrorMessageWSType.....	A-24
A-82	Lookup Return Detail Error Messages	A-26
A-83	Lookup Return Header Error Messages.....	A-29
A-84	Item Lookup Error Messages	A-31
A-85	Item Detail Lookup Error Messages.....	A-34
A-86	Update Return Error Messages.....	A-36
A-87	Lookup Transfer Header Error Messages	A-38
A-88	Lookup Transfer Detail Error Messages.....	A-41
A-89	Update Transfer Error Messages	A-42
A-90	Lookup Markdowns Error Messages.....	A-45
A-91	Process Item Image Error Messages.....	A-47

Send Us Your Comments

Oracle Retail Store Inventory Management Implementation Guide, Volume 4 –
Extension Solutions, Release 13.2.5

Oracle welcomes customers' comments and suggestions on the quality and usefulness of this document.

Your feedback is important, and helps us to best meet your needs as a user of our products. For example:

- Are the implementation steps correct and complete?
- Did you understand the context of the procedures?
- Did you find any errors in the information?
- Does the structure of the information help you with your tasks?
- Do you need different information or graphics? If so, where, and in what format?
- Are the examples correct? Do you need more examples?

If you find any errors or have any other suggestions for improvement, then please tell us your name, the name of the company who has licensed our products, the title and part number of the documentation and the chapter, section, and page number (if available).

Note: Before sending us your comments, you might like to check that you have the latest version of the document and if any concerns are already addressed. To do this, access the Online Documentation available on the Oracle Technology Network Web site. It contains the most current Documentation Library plus all documents revised or released recently.

Send your comments to us using the electronic mail address: retail-doc_us@oracle.com

Please give your name, address, electronic mail address, and telephone number (optional).

If you need assistance with Oracle software, then please contact your support representative or Oracle Support Services.

If you require training or instruction in using Oracle software, then please contact your Oracle local office and inquire about our Oracle University offerings. A list of Oracle offices is available on our Web site at <http://www.oracle.com>.

Preface

The *Oracle Retail Store Inventory Management Implementation Guide – Volume 4, Extension Solutions* guide contains the requirements and procedures that are necessary for the retailer to extend and customize the Store Inventory Management application.

Audience

This document is intended for the Oracle Retail Store Inventory Management application integrators and implementation staff, as well as the retailer's IT personnel.

Documentation Accessibility

Our goal is to make Oracle products, services, and supporting documentation accessible to all users, including users that are disabled. To that end, our documentation includes features that make information available to users of assistive technology. This documentation is available in HTML format, and contains markup to facilitate access by the disabled community. Accessibility standards will continue to evolve over time, and Oracle is actively engaged with other market-leading technology vendors to address technical obstacles so that our documentation can be accessible to all of our customers. For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Accessibility of Code Examples in Documentation

Screen readers may not always correctly read the code examples in this document. The conventions for writing code require that closing braces should appear on an otherwise empty line; however, some screen readers may not always read a line of text that consists solely of a bracket or brace.

Accessibility of Links to External Web Sites in Documentation

This documentation may contain links to Web sites of other companies or organizations that Oracle does not own or control. Oracle neither evaluates nor makes any representations regarding the accessibility of these Web sites.

Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit

<http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Related Documents

For more information, see the following documents in the Oracle Retail Store Inventory Management Release 13.2.5 documentation set:

- *Oracle Retail Store Inventory Management Implementation Guide, Volume 1 – Configuration*
- *Oracle Retail Store Inventory Management Implementation Guide, Volume 2 – Integration with Oracle Retail Applications*
- *Oracle Retail Store Inventory Management Implementation Guide, Volume 3 – Mobile Store Inventory Management*
- *Oracle Retail Store Inventory Management Installation Guide*
- *Oracle Retail Store Inventory Management Operations Guide*
- *Oracle Retail Store Inventory Management Release Notes*
- *Oracle Retail Store Inventory Management User Guide*

Customer Support

To contact Oracle Customer Support, access My Oracle Support at the following URL:

<https://support.oracle.com>

When contacting Customer Support, please provide the following:

- Product version and program/module name
- Functional and technical description of the problem (include business impact)
- Detailed step-by-step instructions to re-create
- Exact error message received
- Screen shots of each step you take

Review Patch Documentation

When you install the application for the first time, you install either a base release (for example, 13.2) or a later patch release (for example, 13.2.5). If you are installing the base release and additional patch releases, read the documentation for all releases that have occurred since the base release before you begin installation. Documentation for patch releases can contain critical information related to the base release, as well as information about code changes since the base release.

Oracle Retail Documentation on the Oracle Technology Network

Documentation is packaged with each Oracle Retail product release. Oracle Retail product documentation is also available on the following Web site:

http://www.oracle.com/technology/documentation/oracle_retail.html

(Data Model documents are not available through Oracle Technology Network. These documents are packaged with released code, or you can obtain them through My Oracle Support.)

Documentation should be available on this Web site within a month after a product release.

Conventions

The following text conventions are used in this document:

Convention	Meaning
boldface	Boldface type indicates graphical user interface elements associated with an action, or terms defined in text or the glossary.
<i>italic</i>	Italic type indicates book titles, emphasis, or placeholder variables for which you supply particular values.
monospace	Monospace type indicates commands within a paragraph, URLs, code in examples, text that appears on the screen, or text that you enter.

Customization

Retailers often modify retail software either in-house or have it modified through third-party system integrators. If the customization efforts are not done properly, the deployed product might not operate correctly. A poorly customized product is difficult to upgrade and deploy. This situation causes serious issues for the retailer, Oracle Retail, and any system integrators involved. This chapter aims to mitigate that risk by providing guidance on how to customize safely and effectively.

Build/Packaging/Deployment Related

To build and deploy customizations correctly, make a separate project for custom-written code. Build a custom JAR with the newly created code. This custom JAR should be placed first in the execution classpath so that classes found within the JAR are chosen by the JVM rather than the base classes. This requires un-signing and re-signing all the JARs in the Oracle Retail Store Inventory Management (SIM)-client application, since all JARs must be signed with the same signature for Web Start to work correctly. Consult the jarsigner documentation from Sun for further information on the JAR un-signing/signing process.

Architecture

Do not connect directly to the RMS or SIM database using JDBC or other database connection software from any client layer, whether that is the PC client, Web Service, or Wavelink server layer. This will lead to being unable to guarantee data integrity and thus SIM can no longer be guaranteed to work.

Process Overview

In order to outline reasonably safe approaches to adding new functionality, this document contains three examples of extensions to the base source code:

- Adding new attributes to pre-existing data and workflows. This includes how to update the database, business and client layers.
- Adding completely new data and workflows to the application including modifying all layers.
- Modifying incoming and outgoing data transport to external systems.

Adding Attribute to Pre-Existing Data & Workflows

To add the attribute **Season** to the current Item object and keep the system open to upgrade without difficulty, do the following:

1. [Add the New Attribute to the Database](#)
2. [Update DAO \(Database Access Objects\)](#)
3. [Update Business Object or Value Object](#)
4. [Update the Services](#)
5. [Update the PC Screen](#)
6. [Update the HH Forms](#)

Add the New Attribute to the Database

The following information describes adding new attributes in a database.

Database Tables

There are two standard categories of database tables in SIM: ARTS tables and SIM-specific tables. ARTS tables are based on industry standard definitions. It might be helpful to know that to decode the names of an ARTS table, read the table name backwards. For example, the PA_STR_RTL table represents Retail Store Party. SIM-specific tables either begin with the RK_ prefix to indicate that they are not part of the ARTS model, or they are named in a forward manner such as STOCK_COUNT or STOCK_COUNT_LINE_ITEM.

Create New Attribute Column

Add the appropriate attribute to SIM's current database table or make a new table to store the attribute. Do not alter or remove any columns as this will render SIM unable to access the table.

SIM's item master is AS_ITM, so add a column to the AS_ITM table that is named GRI_SEASON. Naming should include a unique tag from the company customizing the code in order to easily tell the difference between base and customization for upgrade purposes. If it is decided to add a new item attributes table where SEASON was just one of the attributes, then the name of the table might be GRI_ITEM_ATTRIBUTE. If the entire table is custom, it is then appropriate to simply use the column name SEASON.

Update DAO (Database Access Objects)

The following information describes updating Database Access Objects.

Create DAO Code to Access Information

SIM will not automatically access this new data in the database. Custom DAO (Data Access Object) code must be written to retrieve this information. It is advisable to always create completely new DAO source code for this customization.

You may choose to write data access layer code to retrieve these properties in whatever manner you choose to. However, if you want to use SIM's frameworks for data retrieval and database connection pooling, declare the new data access layer class and have it extend BaseOracleDao:

```
public class ItemAttributeOracleDao extends BaseOracleDao {
```

BaseOracleDao supplies several helpful methods to perform a lot of the heaving lifting of data access. It enables the user to execute() statements, batch statements, and stored procedures as well as perform several different types of queries. Becoming familiar with the Application Programming Interfaces (API)s in this class will help in the process of developing database layer code.

Performing Simple Insert

To perform a simple insert, call the execute() method with a ParametricStatement that contains your insert SQL.

```
String insertSQLString = "insert into GRI_ITEM_ATTRIBUTE (ITEM_ID, SEASON) values
(?, ?)";
```

```
List<Object> insertSQLParams = CollectionUtil.newArrayList();
insertSqlParams.add(itemId);
insertSqlParams.add(season);
```

```
execute(new ParametricStatement(insertSQLString, insertSQLParams));
```

A ParametricStatement is a useful object within the SIM code. It is constructed with the insert SQL string and a list of objects to substitute in the SQL string where "?" appears. Performing a simple update is performed as in the previous example.

Performing Simple Query

To perform a simple query, call the query() method with a ParametricStatement that contains your select SQL:

```
String querySql = "select ITEM_ID, SEASON from GRI_ITEM_ATTRIBUTE where ITEM_ID =
?";
```

```
List<Object> querySqlParams = CollectionUtil.newArrayList();
querySqlParams.add(itemId);
```

```
List<GriItemAttributeDataBean> beans
    = query(new GriItemAttributeDataBean(), querySql, querySqlParams);
```

Using the query helper method of BaseOracleDao will require creating a data bean. A data bean is a simple class that contains the attributes of the table in question. The data bean implements some required API in order to let the framework execute the SQL and then populate the beans with the correct information.

Creating a Data Bean

To create a data bean, create a class that extends BaseDataBean. Implement both the methods defined by the superclass interface:

```
public class GriItemAttributeDataBean extends
BaseDataBean<GriItemAttributeDataBean> {
    private String itemId;
    private String season;
    public String getSelectSql() {
        return "select ITEM_ID, SEASON from GRI_ITEM_ATTRIBUTE where ITEM_ID = ?"
    }
    public GriItemAttributeDataBean read(ResultSet resultSet) throws SQLException
{
```

```

        GriItemAttributeDataBean bean = new GriItemAttributeDataBean ();
        bean.itemId = getStringFromResultSet(resultSet, "ITEM_ID");
        bean.season = getStringFromResultSet(resultSet, "SEASON");
        return bean;
    }
}

```

Update Business Object or Value Object

To customize the attributes on a business/value object within the system appropriately, subclass the business/value object in question and add the attribute to the sub-class only:

```

public class GriItem extends Item {
    private String season;
    public GriItem(String itemId) {
        super(itemId);
    }
    public String getSeason() {
        return season;
    }
    public void setSeason(String season) {
        this.season = season;
    }
}

```

Next, subclass the BOFactoryImpl to override the item creation method and replace it with your own. Once configuration is altered to use the custom factory, everywhere in the code where an Item would have been created/instantiated, a GriItem is instantiated instead:

```

public class GriBOFactoryImpl extends BOFactoryImpl {

    public Item createItem(String itemId) {
        return new GriItem(itemId);
    }
}

```

To configure the item, simply modify the common.cfg file with the classpath of your new code:

```
BO_FACTORY_IMPL=gri.custom.code.GriBOFactoryImpl
```

Update the Services

The same process used to customize the objects within the system is used to override services at the service layer. A subclass of the service is made, followed by pointing the correct configuration file at the subclass instead of the original SIM service:

```

public class GriItemServerServices extends ItemServerServices {
    public StockItem readStockItem(String itemId, Long storeId) throws Exception {
        StockItem stockItem = super.readStockItem(itemId, storeId);
        GriItem griItem = (GriItem) stockItem.getItem();
        griItem.setSeason(new GriItemAttributeDao().selectSeason(itemId));
        return stockItem;
    }
}

```

When overriding an implementation method in the service, it is advisable to call the superclass for standard SIM processing and then perform customized processing afterwards. This ensures continued functionality with future releases.

After creating the customized service, create a customized factory as with the business objects (extending SIM's `ServerServiceFactoryImpl`), and then configure the `common.cfg` file to use your customized factory implementation:

```
public class GriServerServiceFactoryImpl extends ServerServiceFactoryImpl {
    public ItemServices createItemServices() {
        try {
            return new GriItemServerServices();
        } catch (Throwable t) {
            LogService.error(this, "Could not create GriItemServerServices", t);
            return null;
        }
    }
}
```

Example 1-1 common.cfg

```
SERVER_SERVICE_FACTORY_IMPL=gri.custom.code.GriServerServiceFactoryImpl
```

Service Index

The following is a current list of services within SIM:

- ActivityLockingServices
- AdhocCountAdminServices
- AuditLogServices
- BatchServices
- BillOfLadingServices
- ConfigServices
- CustomThemeServices
- CustomerOrderServices
- DealServices
- InventoryAdjustmentServices
- ItemServices
- ItemBasketServices
- ItemRequestServices
- ItemTicketServices
- MdseHierarchyServices
- PollingTimerAdminServices
- PosTransactionServices
- PriceChangeServices
- ProductGroupServices
- ProductGroupScheduleServices
- ReplenishmentServices

- ReportFormatServices
- ReportingServices
- ReturnServices
- SaleReturnServices
- SecurityServices
- SequencingServices
- ShipmentServices
- SourceServices
- StockCountServices
- StockCountLineItemServices
- StockCountLocationServices
- StoreServices
- StoreOrderServices
- TransferServices
- TranslationServices
- UINServices

Update the PC Screen

In order to view or enter additional information on the PC, a new UI space must be created instead of modifying current screens. This is done by adding an additional button to the navigation of the application. In order to add a new button, a new row must be put into the PC_MENU_ITEM table.

Table 1-1 PC_MENU_ITEM Table

Column	Value to Place in Column
MENU	This contains the fully qualified classpath to the screen that contains the menu.
NAME	This is the name of the button to be displayed on the menu. This value is used as a translation key by the client to get the displayable text.
PERMISSION	This is the permission key associated to the button. If the user does not have the assigned permission, the button does not display. Null is valid.
MENU_ITEM_ACTION	This can be one of three values: NONE, BACK or another menu.
MENU_ITEM_ORDER	Buttons are displayed for the MENU in the sequence of lowest to highest MENU_ITEM_ORDER value.
IS_DEFAULT	Y if the button should be the default button for the window. N if not the default button for the window.

If **NONE** is entered in MENU_ITEM_ACTION, then when the navigation button is pressed, no navigation takes place. If **BACK** is entered, then when the navigation button is pressed, the screen navigates to the previous screen in the workflow. If a value matching a MENU column in the table is entered (another menu/screen), then when the navigation button is pressed, the application navigates to the specified screen. In all three of these scenarios, the button action is first sent to the actionPerformed() method of the screen before any navigation takes place.

[Table 1–2](#) is an example record to add a button to the item detail screen:

Table 1–2 PC_MENU_ITEM Table, Item Detail

Column	Value
MENU	oracle.retail.sim.shared.swing.item.ItemDetailScreen
NAME	Additional Details
PERMISSION	null
MENU_ITEM_ACTION	gri.retail.sim.custom.AdditionalItemDetailScreen
MENU_ITEM_ORDER	999
IS_DEFAULT	N

[Table 1–3](#) is an example record to create a menu for the new custom screen:

Table 1–3 PC_MENU_ITEM Table, Custom Screen

Column	Value
MENU	gri.retail.sim.custom.AdditionalItemDetailScreen
NAME	Cancel
PERMISSION	null
MENU_ITEM_ACTION	BACK
MENU_ITEM_ORDER	1
IS_DEFAULT	N

Next, create the `AdditionalItemDetailScreen` class which must extend `SimScreen` and implement all the required methods. After that, design and build the screen (see [Adding New Workflows](#)).

Update the HH Forms

Customizing the HH application is more difficult than other areas of the application. Wavelink does not supply simple or straightforward ways to customize their forms. In order to add additional item information to the HH item lookup workflow, the handheld SIM code source files need to be modified directly.

It is strongly suggested that all new features, information or processes be added with completely new handheld forms. For how to build forms in the Wavelink server, please see Wavelink documentation. Once the new forms are built, a single form may be customized to contain a menu option or command to navigate to the new workflow. This will minimize the amount of rework that needs to be done with each release update of the handheld source code.

Adding New Workflows

Rather than just adding functionality to an existing workflow, this section describes how to add a new workflow to SIM. It focuses on how to design and implement the new workflow to minimize the impact of upgrades to the customization. The example workflow added to the system is the ability to create new serial numbers in an In Stock status without moving them using a system transaction, that is, entering serial numbers into the UIN_DETAIL table without receiving them or creating an inventory adjustment. This type of functionality is used primarily to data seed serial numbers that should have already been in the system.

The following topics will be covered:

- [Building Business Objects](#)
- [Building Enterprise Java Bean \(EJB\) Services](#)
- [Building Data Access](#)
- [Building PC Screens](#)
- [Building Wireless Forms](#)
- [Exceptions](#)

Example Code

This section references example code that is packaged independent of this document. For more information about this example code, see [Appendix: Code Examples](#).

[Table 1–4](#) lists the various files and their general description.

Table 1–4 Example Code Files

Name	Description
CustomSerialNumber	Business object representing the new serial number.
CustomUINBean	The Enterprise Java Bean (EJB) that implements the CustomUINInterface.
CustomUINCountTableEditor	Table editor used in the UI CustomUINCreateScreen.
CustomUINCreateDialog	Pop-up dialog that enables users to enter the new UINs.
CustomUINCreateDialogModel	Model for the pop-up dialog.
CustomUINCreateDialogTableEditor	Table editor used in CustomUINCreateDialog to enter individual UINs.
CustomUINCreateModel	Model for the create screen (track data, talk to server).
CustomUINCreatePanel	Panel for the create screen (contains UI widgets).
CustomUINCreateScreen	Screen for the create screen (interfaces with navigation system).
CustomUINCreateWrapper	A client-side wrapper object for the custom serial number.
CustomUINEJBServices	Client-side EJB Service that looks up and accesses the EJB bean.
CustomUINInterface	Defines the API for Custom UIN EJB.
CustomUINOracleDAO	Database Access Object for custom UIN create logic.

Table 1–4 (Cont.) Example Code Files

Name	Description
CustomUINServerServices	Implementation of CustomUINServices.
CustomUINServices	Defines the API for Custom UIN Services.
CustomUINDataBean	A data bean for a new theoretical CUSTOM_UIN table.

Building Business Objects

In the SIM architecture, business objects represent basic concepts within the Store Inventory Management domain. Some examples of significant objects within SIM are Item, Store, StockCount, Transfer, Shipment and Receipt. Most business objects contain very little business logic. Rather, a business object contains the data associated with the domain concept. The majority of code within a business object concerns itself with getting and setting data values on the business object. The business logic associated with the concept is contained within the ServerServices (or service layer) that uses the business object. Because they contain all the data, business objects flow across all three layers of the SIM architecture.

These business data objects can be designed in any manner as long as they implement Serializable and Cloneable so that they can be used as parameters to server APIs. If the business object extends SIM's BusinessObject class, this is automatically done as well as gaining other useful methods to use.

For more information, see [CustomSerialNumber](#).

The Business Object Class

All SIM business objects extend from the single class BusinessObject. Many classes can be in a hierarchy chain, but BusinessObject should always be the top level object. Refer to the Javadoc for further information. Features provided by the class include:

Table 1–5 BusinessObject Features

Name	Description
isAttributesEqual()	Return true if two values are equal.
isAttributesNotEqual()	Return true if two values are not equal.
isPropertyModifiable()	Return true if the property specified is modifiable; false otherwise. This method makes an executeRule() call, but wraps the call in a try/catch block. If the rule returns an exception, the block catches the exception and returns false , otherwise it returns true . The implementation of the rule is just like that of any other business rule. The rule makes whatever checks are necessary to determine if the attribute is modifiable. It returns a RulesInfo object containing a text message if it is not modifiable, otherwise it returns an empty RulesInfo object. To alter this method, either override the method in business object sub-class (for example, CustomSerialNumber.Java) or configure a rule for the object to execute.
isCoherent()	Returns true if the object is currently coherent. This method makes an executeRule() call. It throws a business exception if the object is not coherent and returns true if it is.
executeRule()	Methods that access the rules engine. This allows business rules to be externally defined against business objects in a configuration file. When a method is called, the rule engine might dynamically load and execute business rules defined for a method.
checkForNullParameter()	Method to determine if a parameter is null and throws a business style exception if it is.

Table 1–5 (Cont.) BusinessObject Features

Name	Description
clone()	A default implementation of clone() is provided. This implementation provides a deep copy of the object. All objects referenced by the business object are also fully copied. Often, this might not be what the developer wants.
cloneShallow()	Clone method that is the same as the standard Java object implementation of clone().
toString()	Uses reflection to convert all attributes of the BusinessObject to a single string.

There are two more types of data objects used within SIM to communicate between the client and server: the query filter and value object.

Query Filter

Business objects represent a single concept of the domain. Sometimes the objects must be selected in groups, often by some criteria, such as finding all employees whose last name begins with T. For those services that require filter criteria, a QueryFilter business object is created. These filters are used in the DAO layer to construct WHERE clauses when selecting and populating the business objects. There is no difference between creating a business object and creating a query filter object (which is also a business object):

```
public class MyQueryFilter extends BusinessObject implements QueryFilter
```

Value Object

A value object (VO) is a trimmed-down version of a business object that contains only the attributes needed for a very specific piece of the application. These objects are created to reduce data flow in areas that do not require that the attributes be updated or any business logic:

```
public class MyVO implements Serializable
```

There is no specific benefit or advantages to creating a value object or query filter other than consistency with naming patterns in SIM while doing customizations.

Customization Using the Rules Engine

The set() methods on business objects and query filters (but not value objects) always call executeRule(). When a method is called, the rule engine might dynamically load and execute business rules defined for a method. This enables business rules to be externally defined against business objects in a configuration file.

Rules are simple classes that validate business logic upon various objects within the system. They are executed primarily when attributes are set() on business objects, but there are also rules accessed when isPropertyModifiable() or isCoherent() are executed. There are already many rules defined in the system. Before creating a new rule, look through existing rules to see if the one you need already exists.

The business rules are located in the numerous .rules packages. If a desired rule does not exist, do the following to create a new rule.

Creating a New Business Rule

To create a new business rule, create a new Java class that extends `SimRule`. This enables the rule to interact with SIM's rule framework.

`QuantityCannotBeNegativeRule` is being used as an example of writing a business rule. This rule passes if the item is sellable and fails if it is not.

```
public final class QuantityCannotBeNegativeRule extends SimRule
```

Override the `execute()` method. This first method performs some brief validation of the args parameters, but the standard coding practice is to break out the args array and cast to specific types to be passed to a second `execute()` method that performs the logic of the business rule. In [Example 1-2](#), the object parameter passed in by the rule engine is not needed. The first parameter of the array is the `Quantity` that needs to be validated:

Example 1-2 Overriding the Execute() Method

```
public RulesInfo execute(Object object, Object[] args) {
    return execute((Quantity) args[0]);
}
```

Implement the typed `execute()` method with the actual logic necessary to perform the desired validation:

Example 1-3 Implementing the Typed Execute() Method

```
private static final RulesInfo RULE_FAILED
    = new RulesInfo(ErrorKey.QUANTITY_INVALID_NEGATIVE);
private RulesInfo execute(Quantity quantity) {
    if ((quantity != null) && (quantity.doubleValue() < 0)) {
        return RULE_FAILED;
    }
    return RULE_PASSED;
}
```

In [Example 1-3](#), `RULE_PASSED` is returned at the end of the validation to indicate that no failure took place. Note that `RULE_PASSED` is actually an empty `RulesInfo` object declared in the `SimRule` super-class that should be used in all subclasses at the appropriate spots.

A `RulesInfo` wrapped around an error string indicates that the rule failed. The framework handles this failed rule information and converts it into the appropriate exception.

Logic in rules is intended strictly for validation checking. The logic should never update or modify the actual object that it is validating. Doing this would violate the contract of the rules engine in SIM and likely leave the business object in a non-coherent state.

Once the rule is developed, the rules configuration file must be updated. Update all occurrences of the `rules_sim.xml` file:

Example 1-4 rules_sim.xml

```
<object className="oracle.retail.sim.closed.invadjustment.InventoryAdjustment">
  <property id="setPackSize">
    <rule_class className=
      "oracle.retail.sim.closed.rules.common.PackSizeMustBePositiveRule"/>
  </property>
  <property id="setQuantity">
```

```

        <rule_class className=
            "oracle.retail.sim.closed.rules.common.QuantityCannotBeNegativeRule"/>
    </property>
    <property id="setComments" propertyNames="setComments">
        <rule_class className=
            "oracle.retail.sim.closed.rules.common.MaxCommentSizeRule"/>
    </property>
</object>

```

This xml file contains a list of classes and rules to execute when certain properties are modified. At the top level, an object is defined with a className containing the complete path to the object on which the validation should be done:

```

<object className="oracle.retail.sim.closed.invalidation.InventoryAdjustment">
</object>

```

Within the class definition is a property definition where the ID is the method signature on which the validation should be performed:

```

    <property id="setQuantity">
    </property>

```

Within the property definition is the rules class definition where className is assigned the fully qualified path to the rule:

```

<rule_class className=
    "oracle.retail.sim.closed.rules.common.QuantityCannotBeNegativeRule"/>

```

Building Enterprise Java Bean (EJB) Services

The next step in creating the workflow is defining the server application programming interface (API) that is accessed to accomplish the work. This means designing an EJB to deploy in the server:

1. Define the Service API (see [CustomUINServices](#)).

Define the exact API to call on the server to perform some logic. These services files might have numerous APIs associated with them.

2. Define the API in an EJB interface (see [CustomUINInterface](#)).

The parameters and return value must be defined as CompressedObject if the API wants to take advantage of SIM's compression during communication between the client and server. A CompressedObject return value should be defined even if the return value is **null** or was defined in step 1 as **null**.

3. Develop the EJB Bean (see [CustomUINBean](#)).

When the EJB bean is developed, extending AbstractSimServiceBean enables quick access to helper methods such as `handleException()`, `getSessionContext()` and `completeServiceContext()`.

The EJB Bean must implement the interface defined in Step 2. In addition, note that to use the compression built in to SIM for quicker performance, even if the service is defined as null, a CompressedObject must be returned. Note that using the try/catch/finally allows the smooth handling of all exceptions and the completion of the service context even if the EJB failed with an exception.

4. Develop EJB Services (see [CustomUINEJBServices](#)).

The EJB Services class is designed to be the client-side of a service call. It handles the task of looking up the EJB Bean, instantiating the compressed objects around the arguments and making the call to the EJB Bean. The EJB Services use the EJBServicesManager to do cached lookups of the EJB Beans for improved performances. Following the pattern in the example is the easiest way to create an EJB Service.

5. Develop EJB Server Service (see [CustomUINServerServices](#)).

The EJB Server Services class contains the actual server side code that performs the business logic of the API. In this particular example, the code only needs to save the new serial numbers, so a Data Access Object (DAO) is instantiated and its API accessed.

6. Deploy EJB Services.

The new EJB Bean needs to be deployed to the server. A system administrator or lead developer should be able to handle this process. The steps are normal steps for deploying an EJB into a server:

- a. The EJB must be packaged in a standard ejb style .jar.
- b. A reference to that .jar must be include in the META-INF/application.xml within the sim-server.ear.

Building Data Access

The next step is to write the DAO that communicates with the database. Using some of SIM's pre-existing tools can simplify this task.

Database Layer Development Tips

- Removing a column from the database breaks the code that attempts to read that table, so do not remove columns.
- New tables should always begin with a custom client-created prefix to keep it easily distinguishable from basic SIM tables. If the company name is Business Company Inc., then a table containing additional item information might be called BCI_ITEM_INFO.
- New columns added to an existing database table should begin with a custom prefix. If a company named Business Company Inc. wanted to add a new column to captured information about a stock count to the stock count header table, it might look like STOCK_COUNT.BCI_EXTRA_DATA.
- All new columns added to the existing tables must be nullable.
- If there is a foreign key reference in newly added tables, then keep the same column name as the table column name it references.
- Do not modify any of SIM's DAOs. Either sub-class and configure the DAO or create a completely new custom DAO.
- Ensure the DAO sub-classes BaseOracleDao so that connection pooling is handled properly.
- Ensure that all data beans sub-class FullDataBean or BaseDataBean.

Creating a DAO

Refer to [Update DAO \(Database Access Objects\)](#) for information about developing new DAOs. Also, refer to [CustomUINOracleDAO](#) for a code example.

The remainder of this section contains suggestions for using general SIM DAO classes. Reading all Javadoc on the following classes will help with knowing all the available APIs available.

Table 1–6 DAO Layer Framework Classes

Name	Description
BaseOracleDao	Abstract base class for all Oracle data access objects. Every DAO implementation must be a sub-class of this object. This class provides a range of generic functionality as well as access to the database connection factory.
BaseDataBean	Abstract base class for all data access beans. Every database bean should have this in its hierarchy.
BatchParametricStatement	Encapsulates SQL and the parameters to be used during its execution. It creates a batch of statements and executes them at the end. This performs much better under the scenario where the same SQL statement is executed multiple times.
FullDataBean	Abstract base class for all data beans that contain select, insert, update and delete functionality.
ParametricStatement	Encapsulates the SQL and the parameters used during the execution of the SQL.
SimStoredProcedure	Interface for any Java code related to stored procedures. Classes implement this interface and are passed to the BaseOracleDao.

DAO Methods

Almost all DAO methods consist of creating a ParametricStatement or BatchParametricStatement and then calling the appropriate execute() method in the BaseOracleDao. In the saveSerialNumbers() method of the custom UIN example, a custom batch SQL statement is built using the UINDetailDataBean class attributes. Regular inserts and updates of a table are much simpler. For example, if a table called CUSTOM_UIN was created to temporarily hold our input, some simpler examples of how the DAO layer works (see CustomUinDataBean.java) might be available.

The following would be the save method in the dao layer using the new data bean:

```
public void saveSerialNumbers(Long storeId, List<CustomSerialNumber>
serialNumbers)
                                                    throws
SimServerException {
    String sql = CustomUinDataBean.UPDATE_SQL
                + where(CustomUinDataBean.COL_ID, CustomUinDataBean.COL_
STATUS);
    BatchParametricStatement batchStatement = new BatchParametricStatement(sql);
    CustomUinDataBean bean = new CustomUinDataBean();

    for (CustomSerialNumber serialNumber : serialNumbers) {
        bean.setId(serialNumber.getId());
        bean.setStatus(UINStatus.IN_STOCK.getCode());
        bean.setStoreId(storeId);
    }
}
```

```

        List<Object> params = bean.toList(false);
        params.add(serialNumber.getId());
        params.add(serialNumber.getStatus().getCode());

        batchStatement.addParams(params);
    }
    executeBatch(batchStatement);
}

```

Building PC Screens

The SIM PC client is a Swing application. It is launched using WebStart and a browser. It communicates with the SIM server through EJBs. The application does not support offline functionality. If communication with the server is lost, an error message is displayed and the client is returned to its login screen.

Note: Because the EJBs are services that run on the server, any client may be written against these remote services. A thin-client application could be written to take advantage of these services if the client wanted some functionality available through Web pages.

Customization Guidelines for the PC

- Always access the EJB services through the ClientServiceFactory class.
- Do not modify any framework-related code.
- To avoid conflicts with updates, only add functionality to client through adding navigation buttons that navigate to custom screens.

PC Client Architecture

The client architecture is broken into five layers, only three of which are worked on to create new or customized PC functionality:

- Application Framework
- <name>Screen
- <name>Panel
- <name>Model
- EJB Service

Application Framework

There is an extensive framework of Swing-related classes used to launch and control the application as well as tools to make working within the Swing client easier. This framework is located in `oracle.retail.sim.closed.swing.*` packages. There is a wide area of functionality covered in this framework from layout tools, to customization tools, to internationalization hooks, to a navigation engine, to advanced tables and advanced widgets. These framework classes should not be modified.

<name>Screen

A screen is the top level of a single PC screen display. Its responsibility is to interact with the navigation system and delegate the actions of its menu items to the panel (see [CustomUINCreatePanel](#)).

<name>Panel

The panel is where all the visual elements of a single PC screen are located. All the Swing widgets are declared here as well as any functional logic that touches those widgets (getting and setting the widget properties and values). All logic not associated directly with the widgets is delegated to the model (see [CustomUINCreatePanel](#)).

<name>Model

The model is where all access to the service layer takes place as well as any complex logic that needs to take place on the client is written (see [CustomUINCreateModel](#)).

EJB Service

An EJB service is accessed through the ClientServiceFactory (or custom written EJB service) and should only be done from the application framework or from the model layer.

Navigation

There is both configurable navigation and hard-coded navigation within the SIM application.

External Configurable Navigation The primary means of navigation in the PC application is through pressing the menu buttons displayed at the top of the screen. These menu buttons are determined using the information in PC_MENU_ITEM in the database. Adding, editing, and removing buttons for customization must be done within by adding or altering information in this database table. See [Update the PC Screen](#) for more information.

Hard-Coded Navigation The ability to navigate from within the <name>Screen or <name>Panel class is supplied in the framework by the navigate() and navigateLater() methods found in SimScreen and ScreenPanel classes. There are two different ways that hard-coded navigation takes place. The DirectDeliveryDetailScreen/Panel is an excellent example of this. Because it can be reached through screens that should not be returned to using the standard framework, very specific navigation is coded for the screen.

For example, in the handleDelete() method, the application return to the previous screen only if the direct delivery is successfully cancelled. This is done using the SimNavigation.BACK value as the navigate parameter. The remainder of the values in SimNavigation are the identities of the buttons used within the application:

```
public void handleDelete() throws Exception {
    lineItemTable.stopEditing();
    // Rest of method code removed
    if (model.isDirectDeliveryEmpty() && cancelEmptyDelivery()) {
        navigate(SimNavigation.BACK);
    }
}
```

Screens

A screen is the top level of a single PC screen display. The primary responsibility of screens is to interact with the navigation framework. The following is a break-down of the structure of screens. Use these coding guidelines when creating a customized screen. The example is the new CustomUINCreateScreen built to add the customized functionality of creating UINs without going through a transaction.

1. The UI screen must extend `SimScreen`. Usually, the only declaration is the panel that the screen delegates to. In some rare cases, variables may need to be declared to track some value at the screen level. Declare the constructor, which never contains parameters and simply adds the panel using the `add()` method available on the superclass.

Implement the `getScreenName()` method. This should return the title of the screen to be displayed.

```
public class CustomUINCreateScreen extends SimScreen {
    private static final long serialVersionUID = 487712289865375658L;
    private CustomUINCreatePanel panel = new CustomUINCreatePanel();
    public CustomUINCreateScreen() {
        add(panel);
    }
    public String getScreenName() {
        return "UIN Create";
    }
}
```

2. Implement and `start()` method. This method is called whenever the screen is navigated to. The `start()` method is called as the navigation takes place. Of interest are the two lines of code that are found in nearly every `start()` method. `showMenu()` causes the menu of the screen to be displayed. Passing in a parameter assigns a default button for the screen. The call to `panel.start()` triggers the startup of the visual panel. There can be a wide variety of functionality necessary in the startup of a screen, but it is important to remember that all functionality should be delegated to the panel except for what is related to navigation. The `start()` method may throw an exception which will halt the navigation to the screen.

```
public void start() throws Throwable {
    showMenu();
    panel.start();
}
```

3. Implement the `stop()` method. This method is called whenever the screen is exited. Place code in here to clean up the state of the screen. This method can never throw an exception.

```
public void stop() {
    panel.stop();
}
```

4. Implement the `resume()` method if necessary. Resume is executed when the screen is navigated away from, but has not disappeared from the chain of screen. When the screen is returned to (such as from a sub-screen, this method is called to resume the screen). The `resume()` method should always call `showMenu()` to reset which buttons should be visible. The super-class `SimScreen` has a default implementation:

```
public void resume() {
    showMenu();
}
```

5. There are two new methods:

- isStartable()
- isStoppable()

They are checked before start() and stop() are called respectively when screen navigation is taking place. Screen state validation code can be placed in these methods. If isStartable() returns **false**, the screen will not allow itself to be navigated to. If isStoppable() returns **false**, the screen will not allow itself to be navigated away from:

```
public boolean isStartable() {
    return panel.isStartable();
}
```

6. Override the navigationEvent() method from the superclass. All menu buttons create NavigationEvent objects and pass them to the screen through this method. Each event has a command value that matches the button that pressed it. The implementation of this method should determine which button is pressed and delegate to the appropriate panel method:

```
public void navigationEvent(NavigationEvent event) {
    String command = event.getCommand();
    try {
        if (command.equals(SimNavigation.ADD_ITEM)) {
            panel.doAddItem();
        } else if (command.equals(SimNavigation.DELETE_ITEM)) {
            panel.doDeleteItem();
        } else if (command.equals(SimNavigation.DONE)) {
            panel.doHandleDone();
        }
    } catch (Throwable exception) {
        displayException(panel, event, exception);
    }
}
```

Features of the Screen The SimScreen superclass contains several features that can be used by all subclasses. A brief listing is supplied in [Table 1-7](#).

Table 1-7 Features of the Screen

Feature	Description
assignFocusInScreen()	Assigns focus to the first button on the navigation menu.
navigate()	Navigates to the specified screen.
navigateLater()	Navigates to the specified screen on a separate thread.
removeFromScreenHistory() ()	Removes the screen from the navigational history.
removeNavButton()	Removes a navigational button from the menu.
displayException()	Displays the exception in the error dialog.

Screen Panels

The panel is where all the visual elements of a single PC screen are located. All the Swing widgets are declared here as well as any functional logic that touches those widgets (getting and setting the widget properties and values). All logic not associated directly with the widgets is delegated to the model. The following shows some of the basic principles of designing a panel (see [CustomUINCreatePanel](#)):

1. Declare the panel. The new panel should extend the `ScreenPanel` class.

```
public class CustomUINCreatePanel extends ScreenPanel implements REventListener
{
    private CustomUINCreateModel model = new CustomUINCreateModel();
```

2. Declare Editors and Tables. Declare the editors and tables that will be used within the panel. There should be an editor for each style of data currently used in SIM. See [Editors](#) for further detail. `SimTable` is the most common type of table used in SIM. `SimTable` should be placed within a `SimTablePane`.

```
private StockItemTableEditor stockItemTableEditor = new StockItemTableEditor();
private SimTable stockItemTable = new SimTable(new
CustomCreateUINTableDefinition());
private SimTablePane stockItemPane = new SimTablePane(stockItemTable);
```

3. Declare Constructor. The constructor of a panel is expected to not take any parameters and not throw any exceptions:

```
public CustomUINCreatePanel() {
    initializePanel();
    layoutPanel();
}
```

4. Initialize the Panel. The following is an example of initializing the property settings on editors and tables:

```
private void initializePanel() {
    stockItemTableEditor.addTableEditorListener(buildStockItemListener());
    stockItemTable.setColumnSize("serialNumberCount", SimTable.LABEL_WIDTH);
}
private void layoutPanel() {
    setContentPane(stockItemPane);
}
```

5. Start the Panel. A `start()` method should be created so that the screen can call it to load the panel with information. Note that if a default focus editor is desired, the `assignFocusInScreen()` method should be called at the end of start passing in the component to receive focus.

```
public void start() throws Throwable {
    stockItemTable.addRow(new CustomUINCreateWrapper());
}
```

Editors

Table 1–8 is a brief list of common UI data editors used in SIM and what they do.

Table 1–8 Editors

Editors	Description
RCheckBoxEditor	A check box that can be selected or de-selected.
RComboBoxEditor	A combo box list of selections.
RDateFieldEditor	A single date field that can be edited by hand or through a calendar.
RDateRangeEditor	Two date fields that represent a start date and end date.
RDecimalFieldEditor	A text field that only allows decimal numbers to be entered.
RDisplayLabelEditor	An object displayer that does not allow editing.
RIntegerFieldEditor	A text field that only allows integer numbers to be entered.
RListEditor	A scrollable list of selections.
RLongFieldEditor	A text field that only allows long numbers to be entered.
RLongTextFieldEditor	A text field with an expansion dialog associated to it, often used for very long text fields that must take up limited screen space.
RMoneyFieldEditor	A text field that only allows money values to be entered.
RNumericIdEditor	A text field that edits numeric-only identifier strings.
RPasswordFieldEditor	A text field that allows the hidden entry of a password.
RPercentFieldEditor	A text field that only allows percent values to be entered.
RQuantityEditor	A text field that only edits Quantity values.
RRadioButtonEditor	An editor that allows a set of option buttons to be displayed and selected.
RSearchComboEditor	An editor that present a combo box of values but allows the user to trigger a search for additional values.
RSearchFieldEditor	A text field that allows the user to enter a value or search for one.
RTextAreaEditor	A large text area where large quantities of text can be edited.
RTextFieldEditor	A single line text field where small quantities of text can be edited.

Initializing Editors The editors are customized to contain numerous properties beyond those of the normal Swing widgets. Many of the customized properties are just short-cuts to other work. Here is a sample of some initialization in the `InventoryAdjustmentFilterDialog`. This includes setting displayers (which are responsible for formatting data), setting general size properties for the editors, and assigning an identifier to a text entry field (without an identifier, the editor will not activate).

Example 1–5 `InventoryAdjustmentFilterDialog`

```
private void initContent() {
    adjustmentEditor.setIdentifier(SimName.INVENTORY_ADJUSTMENT_NUMBER);
    adjustmentEditor.setEntryAlignmentLeft();
    adjustmentEditor.setSizeType(EditorConstants.MEDIUM);
    statusEditor.setDisplayer(new TranslatedObjectDisplayer());
    statusEditor.setSizeType(EditorConstants.LARGE);
    statusEditor.setEmptyType(RComboBoxEmptyType.ALL);
}
```

Editor Layout To lay out editors in a simple grid, use an `REditorPanel`. Declare the rows and columns when instantiating and add editors to the panel. The `REditorPanel` handles all the layout details:


```
private void layoutContent() {
    REditorPanel miscFilterPanel = new REditorPanel(6);
    miscFilterPanel.setTitleBorder("Additional Filters");
    miscFilterPanel.add(itemEditor);
    miscFilterPanel.add(reasonEditor);
    miscFilterPanel.add(userEditor);
    miscFilterPanel.add(adjustmentEditor);
    miscFilterPanel.add(statusEditor);
    miscFilterPanel.add(searchLimitEditor);
}
```

Search Editor

A search editor is an editor that enables a user to enter data or find data. It consists of an editable text field that allows the user to enter an ID, a button that allows the user to search, and a non-editable text field that displays the description. The `InventoryAdjustmentFilterDialog` has a search editor for its item value that will be used as an example.

If an ID is entered, the editor automatically searches for the whole object. When the button is clicked, the screen navigates to a dialog where an object is chosen. Upon return, the data of the object is displayed:

Figure 1–1 *InventoryAdjustmentFilterDialog*



Using a Search Editor Do the following to declare and implement a search editor. Examples are from `InventoryAdjustmentFilterDialog`.

1. Declare the search editor.

```
private RSearchFieldEditor itemEditor =
    SimEditorFactory.createItemVOSearchFieldEditor(false);
```

- Set all the properties of the search editor. The following basic properties are required for a search editor to function:

Table 1–9 Search Editor Properties

Property	Description
identifier	The identifier is a component's name and can be used to reference the component uniquely.
search processor	The search processor is a class that implements the SearchProcessor interface. When the ID is altered in the entry field, this processor will be triggered to attempt to find the information.
search listener	The search listener is a class that implements the SearchListener interface. This class will be called when the Search button is pressed.

Example of setting up the properties of the search editor:

```
itemEditor.setIdentifier(SimName.ITEM_ID);
itemEditor.setSearchProcessor(new
ItemVOSearchProcessor(allowNonInventoryItems));
itemEditor.setSearchListener(buildItemSearchListener());
```

- Build a search listener. A search listener needs to be declared independently for each search editor that is used. This class must implement the SearchListener interface. Basically, it contains the method that is called once the data is found.

```
private ItemSearchListener buildItemSearchListener() {
    return new ItemSearchListener() {
        public void assignItem(ItemVO itemVO) {
            if (itemVO != null) {
                itemEditor.setData(itemVO);
            }
        }
    };
}
```

- Build a search processor. A new search processor must implement the SearchProcessor interface. It must return a display for the entry area of the widget, a display for the value area of the widget, it must implement the searchById() method to find the appropriate object can put in a method that validates the data.

```
public class UserSearchProcessor implements SearchProcessor {
    private AttributeDisplay entryDisplay = new
AttributeDisplay("userName");
    private DualAttributeDisplay valueDisplay
        = new DualAttributeDisplay("firstName", "lastName",
StringConstants.SPACE);

    public Object searchById(String userName) throws Exception {
        User user = ClientServiceFactory.getSecurityServices().readUser(userName);
        if (user == null) {
            UIException exception = new UIException(ErrorKey.USER_NOT_FOUND);
            exception.addValue(userName);
            throw exception;
        }
        return user;
    }

    public BasicDisplay getEntryDisplay() {
        return entryDisplay;
    }
}
```

```

    public BasicDisplayer getValueDisplayer() {
        return valueDisplayer;
    }
    public Object validateData(Object data) {
        return data;
    }
}

```

SimTable

SimTable is an extension of JTable that allows the display and editing of cells and data. It contains advanced options not available with the standard table. It is also specifically designed to handle common design patterns in SIM.

Using a SimTable Declare the SimTable globally within the panel. It requires passing in a table definition. The SimTable should be placed within a SimTablePane and the pane added to the layout. SimTablePane supplies the scrollbars for the table:

Example 1-6 CustomUINCreatePanel

```

private SimTable stockItemTable = new SimTable(new
CustomCreateUINTableDefinition());
private SimTablePane stockItemPane = new SimTablePane(stockItemTable);

```

When initializing the screen panel, set desired properties on the table. In the example workflow code, we limit the size of the serial number count column to the width of its label. In the ItemLookupPanel code we show an example of other simple features of the table being applied.

Example 1-7 CustomUINCreatePanel

```

stockItemTable.setColumnSize("serialNumberCount", SimTable.LABEL_WIDTH);

```

Example 1-8 ItemLookupPanel

```

itemTable.setTableEditable(false);
itemTable.setSingleRowSelectionMode();
itemTable.registerDoubleClickAction(this, ITEM_SELECTED);

```

Assigning data to the table is simply a matter of passing a collection of objects to be displayed. The setRows() method automatically replaces all the content of the table. The objects must all be of the class type declared in the table definition. There are other common methods for dealing with data such as addRow(), insertRow(), updateRow() and removeRow() that simply take the data object to be displayed in the row.

Example 1-9 ItemLookupPanel

```

itemTable.setRows(model.findItemVOs(searchFilter));

```

Example 1-10 CustomUINCreatePanel

```

stockItemTable.addRow(new CustomUINCreateWrapper());

```

Retrieving information from the table is as simple as using the various available get() methods such as getSelectedRow(), getSelectedRowData(), getAllSelectedRowData(), and getAllRowData(). Methods ending in Data retrieve the object represented by the row, so getSelectedRow() returns the row index, whereas getSelectedRowData() returns the row object. For example, see the doDeleteItem() and doHandleDone() methods in [CustomUINCreatePanel](#).

SimTableDefinition A table definition is the core of how a table works. To create a table definition, develop a class (public or inner private) that extends `SimTableDefinition`, and then implement the required methods. See `CustomCreateUINTableDefinition` in `CustomUINCreatePanel` as an example of this class. [Table 1–10](#) is a quick summary of APIs on `SimTableDefinition` class.

Table 1–10 *SimTableDefinition APIs*

API	Description
<code>getIdentifier()</code>	The unique identifier of the table. This API is used to track configuration information. The default implement is <code>declaringClassName.className</code> .
<code>getSortAttributes()</code>	Retrieves the list of default sort attributes. If the table configuration does not have any sort configuration settings, these sort attributes will be used to generate the initial sort configuration.
<code>getOverrideEditableAttributes()</code>	Retrieves a list of attributes that do not require having a <code>setter()</code> method on the model in order to be considered editable in a table.
<code>getDataClass()</code>	The Class object of the data that each row in the table represents. This operates as the model for a row.
<code>getAttributes()</code>	A list of SIM table attributes that represent the attributes of each column.

In some cases, a single row of the table actually represents data that is originally from two different business objects. In the case of a table where the column definitions do not match with a data class one-for-one, a wrapper class should be created to wrap the data objects. The wrapper will contain the actual data, but have method APIs that represent the columns in the table.

SimTableAttribute A `SimTableAttribute` represents exactly one column within the `SimTableDefinition`. There are many different properties that can be assigned to the object. See `CustomUINCreatePanel` for the example of `CustomCreateUINTableDefinition`:

Title

The title is displayed as the column header. This text label is actually a key into the translation tables. This key is also used as a unique identifier for the column.

Attribute

The second parameter is the attribute of the column. The value represents a getter and setter on the class type for retrieving the data. For example, if `shortDescription` is the attribute, then `getShortDescription()` and `setShortDescription()` should exist on the class type defined in the `getDataClass()` method. The attribute should always begin with a lower case letter. If a period appears within the attribute, then multiple levels of method calls will take place. For example, the attribute `one.two.three` would be converted into `getOne().getTwo().getThree()` when attempting to retrieve the column information from the data class. However, layered method calls like this are a good indicator that a wrapper or value object needs to be created.

Displayer

Each attribute value is examined by the table during instantiation and default displayers are assigned for the data type belonging to the attribute. If the attribute is a `Quantity`, then a `QuantityDisplayer` is assigned; if the attribute is a `Boolean`, then a `BooleanDisplayer` is assigned, and so on. If the attribute requires specialized formatting, then a displayer should be assigned to the attribute manually. In the example, an `AttributeDisplayer` is assigned to the `stockItem` attribute and a `UOMModeDisplayer` is assigned to the `unitOfMeasureMode` attribute.

Table Editor

Each attribute value is examined by the table during instantiation and default table editors are assigned for the data type belonging to the attribute. If the attribute is a Quantity, then a QuantityTableEditor is assigned; if the attribute is a Boolean, then a BooleanTableEditor is assigned, and so on. If the attribute requires specialized editing, then a table editor should be assigned to the attribute manually. In our example, a StockItemTableEditor is assigned to the stockItem attribute. The StockItemTableEditor is declared at the class level so it can be modified by class code.

Editable

Should be assigned true if the column allows editing, false otherwise.

Displayers Displayers are a hierarchy of classes responsible for formatting the information of an object into a displayable string. Each displayer must implement the method `getDisplayText()`. The package `oracle.retail.sim.closed.swing.displayer` in the client project contains numerous useful generic displayers.

Creating a New Displayer Use the following procedure to create a new displayer as needed:

1. Check all previously existing displayers. Many of the generic displayers can handle formatting different objects (such as `AttributeDisplayer`, `DualAttributeDisplayer` and `DefaultDisplayer`).
2. Design the new displayer and extend the appropriate superclass (often `AbstractDisplayer`).
3. Implement the `getDisplayText()` methods.

Example 1–11 StoreDisplayer

```
public class StoreDisplayer extends AbstractDisplayer {
    private String separator = " - ";
    public String getDisplayText(Object object) {
        if (object == null) {
            return StringConstants.EMPTY;
        }
        if (object instanceof BuddyStore) {
            BuddyStore store = (BuddyStore) object;
            return store.getBuddyId() + separator + store.getBuddyName();
        }
        if (object instanceof Store) {
            Store store = (Store) object;
            return store.getId() + separator + store.getName();
        }
        if (object instanceof SimStore) {
            SimStore store = (SimStore) object;
            return store.getId() + separator + store.getName();
        }
        return object.toString();
    }
}
```

The Displayable Interface There is an interface named `Displayable` with a single method `toDisplayString()`. This is intended to be implemented by wrappers, business objects and any other type of object that might need to have a display value, but which the `toString()` method is primarily reserved for debugging. Currently, `Store` is the only object to implement `Displayable`. The UI framework is already set up to recognize and use `Displayable`. For example, if you drop several `Displayable` objects into an `RComboBoxEditor`, it automatically calls `toDisplayString()` to determine what to display.

Example 1–12 StoreDisplayer

```
public class Store extends BusinessObject implements Displayable {
    public String toDisplayString() {
        return id + " - " + name;
    }
    public String toString() {
        StringBuilder buffer = new StringBuilder();
        buffer.append("Store: [");
        buffer.append("Id: ").append(getId());
        buffer.append("; Name: ").append(getName());
        buffer.append("; Language: ").append(getLanguage());
        buffer.append("; Country: ").append(getCountry());
        buffer.append("; Currency: ").append(getCurrencyCode());
        buffer.append("; Sim flag: ").append(getSimFlag());
        if (timezone != null) {
            buffer.append("; Timezone: ");
            buffer.append(timezone.getDisplayName());
        }
        buffer.append("]");
        return buffer.toString();
    }
}
```

TableEditors Like the editors designed to be used on screens, table editors are advanced widgets designed for use within table cells. The `SimTable` uses the `SimTableEditor` interface to control editing within `SimTable` cells.

- `CustomUINCreateDialogTableEditor` is included in the example code set as an implementation of a normal table editor.
- `CustomUINCountTableEditor` is included in the example code set as an implementation of a table editor that opens a dialog box.

There are many generic table editors located within the client project in `oracle.retail.sim.closed.swing.tableeditor` package. If these do not meet requirements, there are SIM-specific table editors within the client project in the package `oracle.retail.sim.close.swingclient.tableeditor`. If these do not meet requirements, a custom table editor must be written.

Note: No specific documentation on creating table editors is planned for this document. Table editors are complicated objects that require very precise design. Design and code review for any new table editors should be performed by a senior developer.

Table Wrappers and Value Objects

When creating a table definition, the `getDataClass()` is used to specify what object is being displayed. Often, the definition of a row does not exactly match a business object. Sometimes a row might require two business objects. Sometimes the API of the business object does not match what is desired for display. Design of the business layer and its objects should be done strictly with the idea of capturing functional requirements, relationships and behavior, and not necessarily with how the business layer and its objects are gathered and displayed on the screen.

There are two methods of dealing with a row that does not cleanly map to a business object:

Wrappers

Wrappers are UI objects that wrap one or more business objects into a single API that the table can easily access and modify. This creates an isolated layer between the table and business object where the UI client code can live that does not belong to the behavior of the business object.

[Example 1–13](#) is a poor example, as it directly uses the business object `ReceiptLineItem`:

Example 1–13 *DirectDeliveryDetailPanel*

```
private static class DirectDeliveryItemDefinition implements SimTableDefinition {
    public Class getDataClass() {
        return ReceiptLineItem.class;
    }
}
```

[Example 1–14](#) is a good example, as it uses a wrapper for the direct delivery line item that represents an interface to the table:

Example 1–14 *DirectDeliveryDetailPanel*

```
private class DirectDeliveryItemDefinition extends SimTableDefinition {
    public Class getDataClass() {
        return DirectDeliveryLineItemWrapper.class;
    }
}
```

A wrapper simply wraps another object or objects and has methods that are designed for the table and its column. The wrapper determines what to do with the code and passes it on to the business objects. Note how the wrapper contains both a stock item and the serial number values to add. This makes it convenient to create one table row API that accesses both objects:

Example 1–15 *CustomUINCreateWrapper*

```
public class CustomUINCreateWrapper {
    public static final String STOCK_ITEM_PROPERTY = "stockItem";
    public static final String DESCRIPTION_PROPERTY = "description";
    public static final String UIN_COUNT_PROPERTY = "serialNumberCount";
    private StockItem stockItem;
    private List<SerialNumberValue> serialNumbers = CollectionUtil.newArrayList();
    public StockItem getStockItem() {
        return stockItem;
    }
}
```

Value Objects

Value Objects are end-to-end objects that represents a summary or partial view of one or more objects. Value objects should be designed to clean representations of the data matching exactly where they are going to be used. Value objects do not execute rules or contain setters. They contain only getter methods and doSet() methods that should only be used by the DAO layer. They also tend to declare only basic data they need and not contain complete objects. A value object should only be used within the code when the row of the table is not going to be edited, as the value object is considered unchangeable. The ItemVO is a good example of this pattern. This value object is designed to primarily be used on the ItemLookupPanel (which does not edit any information) and so its information matches the screen.

Example 1–16 ItemVO

```
public class ItemVO implements Serializable, ItemDescription {
    private String id = "";
    private String shortDescription = "";
    private String longDescription = "";
    private SupplierVO supplierVO = null;
    private String departmentName = "";
    private String className = "";
    private String subclassName = "";
    private boolean isRanged = true;
    private ItemType itemType = ItemType.ITEM;
    public ItemVO(String id) {
        this.id = id;
    }
    public String getId() {
        return id;
    }
    public String getShortDescription() {
        return shortDescription;
    }
}
// Remainder of code...}
```

In this example, note how the ItemVO contains departmentName instead of an ID or the full merchandise hierarchy node. This is because the name is the only item required where the VO is used. The same with adding the flag isRanged(), which a normal item does not contain. This makes the item much smaller and easier to transmit across the service call.

Triggering User Interface Events Sometimes, a user might want to perform an action and execute some logic when an event occurs within the components on the screen. Under these circumstances, there is a specific framework in place to accomplish this. Whenever possible, avoid using standard Swing listeners to accomplish these kinds of tasks, instead using REventListeners and RActionEvents:

Regular Editor Actions

Do the following to receive and process actions. Almost all actions of this nature take place within the Panel code.

1. Register an action on an editor.

Every editor within the system implements RetailEditor that contains the method registerAction(). There are two parameters: the listener and the command. When the contents of the editor change, the listener is notified with the command.

Actions are normally registered within the initializePanel() method of the Panel.

Example 1–17 DirectDeliveryCreatePanel

```
private RSearchFieldEditor itemEditor =
    SimEditorFactory.createNonRangingItemSearchFieldEditor("Item");
private RSearchFieldEditor supplierEditor =
    SimEditorFactory.createSupplierSearchFieldEditor();
private static final String ITEM_MODIFIED = "Item.modified";
private static final String SUPPLIER_MODIFIED = "Supplier.modified";

private void initializePanel() {
    // Additional Code Here
    itemEditor.registerAction(this, ITEM_MODIFIED);
    supplierEditor.registerAction(this, SUPPLIER_MODIFIED);
    // Additional Code Here}

```

2. Receive and parse the action.

All `RActionEvents` that are generated are sent to the method `performActionEvent()`. The method should parse out which action took place in the standard pattern and delegate to a method to execute the logic. This pattern is preferable to creating inner class listeners on the fly because there is one centralized place within the panel to find where all actions are being delivered. This pattern also aids debugging as well.

Example 1–18 DirectDeliveryCreatePanel

```
public void performActionEvent(RActionEvent event) {
    String command = event.getEventCommand();
    try {
        if (command.equals(TYPE_SELECTED)) {
            doRadioSelectionModified();
        } else if (command.equals(ITEM_MODIFIED)) {
            doItemModified();
        } else if (command.equals(ITEM_SUPPLIER_MODIFIED)) {
            doItemSupplierModified();
        } else if (command.equals(SUPPLIER_MODIFIED)) {
            doSupplierModified();
        } else if (command.equals(PO_MODIFIED)) {
            doPurchaseOrderModified();
        } else if (command.equals(PACK_ITEM_MODIFIED)) {
            doPackItemModified();
        } else if (command.equals(PACK_MODIFIED)) {
            doPackModified();
        } else if (command.equals(PACK_SUPPLIER_MODIFIED)) {
            doPackSupplierModified();
        }
    }
    catch (Throwable e) {
        displayException(e);
    }
}

```

3. Implement the action logic.

Implement the private method that executes the logic associated with the editor.

Table Editor Actions

Editors within tables can be listened to in order to receive events, but they are handled in an entirely different manner.

Use the `addTableEditorListener()` method to add a listener to the table editor. A table editor can either be declared as a class variable so it is handy or can be retrieved from the table itself based on the type of property that is being modified.

Build a listener. Use a `build<name>Listener` method to get the code separated into a convenient method rather than declaring inline where it might obfuscate what is taking place. In the following example, every time the stock item value changes within the table, the `validateEnabledState()` method is called within the panel:

Example 1–19 ReturnDetailPanel

```
private StockItemTableEditor stockItemTableEditor = new StockItemTableEditor();
private void initializePanel() {
    stockItemTableEditor.addTableEditorListener(buildStockItemListener());
}
private SimTableEditorListener buildStockItemListener() {
    return new SimTableEditorListener() {
        public void performTableEditorEvent(SimTableEditorEvent event) {
            validateEnabledState();
        }
    };
}
```

Screen Models

Screen models hold onto the state of data or information and interact with the business layer of the system for the panel of UI widgets. The following is an example of building a screen model (using the `CustomUINCreateModel.java` found in the example code):

1. Declare the model. The model must extend `SimScreenModel`. Declare any variables, usually the data the model represents. No constructor is necessary for a model as there are never any parameters passed into a model constructor.

```
public class CustomUINCreateModel extends SimScreenModel {
    private String CUSTOM_UIN_SERVICES_KEY = "CUSTOM_UIN_SERVICES_KEY";
```

2. Add all the functional methods required by the panel to communicate with the server or manipulate data on a logic level. Here is an example of common methods found in a model.

```
public void saveSerialNumbers(List<CustomUINCreateWrapper> wrappers) throws
Exception {
    List<CustomSerialNumber> serialNumbers = CollectionUtil.newArrayList();
    for (CustomUINCreateWrapper wrapper : wrappers) {
        for (SerialNumberValue value : wrapper.getSerialNumbers()) {
            CustomSerialNumber serialNumber = new CustomSerialNumber();
            serialNumber.setId(value.getUINDetailId());
            serialNumber.setStatus(value.getStatus());
            serialNumbers.add(serialNumber);
        }
    }
    getCustomUINService().moveSerialNumbersToInStock(serialNumbers);
}
```

Features of the Model The SimScreenModel superclass contains several features that can be used by all subclasses. A brief listing is supplied in [Table 1–11](#).

Table 1–11 Model Features

Feature	Description
getUser()	Retrieves the current user logged into the application.
getStore()	Retrieves the current store the user is logged into.
getAllowedStores()	Retrieves a list of stores the user is allowed to access.
getTimeZone()	Retrieves the time zone of the current store.
hasPermission()	Returns true if the user has the specified permission.
hasDataPermission()	Returns true if the user has the specified permission for a particular piece of data.
releaseLock()	Release an activity lock on the transaction being used.
confirmLock()	Confirms the current user still holds the activity lock on the transaction being used.
obtainLock()	Obtains an activity lock for a user on a transaction.
buildExceptionWithValue())	Creates a UIException where there is a substitute value within the message.

Dialog Windows

There are a few different usages of dialog boxes in SIM. The most common usage is to display errors, messages and confirmations during the workflow process. Other usages include pop-up search dialogs (item & supplier) and entering data.

Error & Message Dialogs The developer never instantiates or creates an error or message dialog. These types of dialogs are handled entirely by the framework. Models cannot display errors because they only represent logic, so all exceptions must be propagated to the Panel or Screen level where helper methods exist to display the exceptions. The `displayMessage()` and `displayWarning()` methods take a string and display a message window. These methods are only available at the panel level as the screen level is thin enough to not need these methods. [Figure 1–20](#) in `ItemTicketListPanel` uses several different helpers all in one method:

Example 1–20 ItemTicketListPanel

```
private void printTickets() throws Exception {
    try {
        List<ItemTicketWrapper> wrappers =
itemTicketTable.getAllSelectedRowData();
        String message = model.printTickets(wrappers);
        if (message != null) {
            displayMessage(Translator.getMessage(message));
        }
    } catch (NoPrinterDefinedException noPrinterException) {
        displayError(noPrinterException.getMessage());
    } catch (BusinessException exception) {
        displayException(exception);
    } finally {
        itemTicketTable.setRows(model.findItemTickets());
    }
}
```

Confirmation Confirmation dialogs are Ok/Cancel or Yes/No dialogs that allow the user to make decisions. Confirmation dialogs are not instantiated. A utility class (RConfirmUtility) is supplied to make the display of confirmation dialogs easier. The confirm() method returns **true** if the option was confirmed; **false** if it was not.

[Example 1-21](#) and [Example 1-22](#) show some different usages of the confirmation utility:

Example 1-21 ReturnDetailPanel

```
protected boolean cancelReturn() throws Exception {
    if (RConfirmUtility.confirmWithOkCancelType("Delete Return Confirmation",
        SimClientErrorKey.RETURN_MISSING_QUANTITY)) {
        model.cancelReturn();
        return true;
    }
    return false;
}
```

Example 1-22 MacroSequenceListPanel

```
public void handleApplyClassList() throws Exception {
    if (model.isSequenceCoherent()) {
        if (RConfirmUtility.confirm("Confirmation",
            SimClientErrorKey.SEQUENCE_GENERATE_LOCATION_
CONFIRM)) {
            LocationArea locationArea = LocationArea.BACKROOM;
            if (RConfirmUtility.confirm("Select Area",
                SimClientErrorKey.SEQUENCE_SHOPFLOOR_OR_BACKROOM, "Shopfloor",
"Backroom")) {
                locationArea = LocationArea.SHOPFLOOR;
            }
            try {
                model.applyClassList(locationArea);
            } catch (BusinessException exception) {
                displayException(exception);
            }
            locationTable.setRows(model.findLocations());
        }
    }
}
```

Pop-up Windows All pop-up windows have RDialog as a super-class. If the customization includes popping up a dialog window to enter data, then by using RDialog as the super-class, the customized code can access several additional useful methods connected to SIM's framework.

Building Wireless Forms

The SIM Wireless handheld client is a Wavelink application. All wireless clients (users in the store) use handheld physical devices to talk to a wireless container (sometimes called the wireless server). Most of the SIM application can be accessed through these handheld devices. In certain areas such as stock counts and product groups, some administrative tasks must be done on the PC as these tasks cannot be performed by the handheld device.

Wireless Application Architecture

The client architecture is broken into five layers, only three of which are worked on during application development:

Wireless Framework This is the wireless framework application consisting of the Wavelink code that starts and executes as a server and handles the actual communication protocol back and forth to the handheld devices.

Form_<name> The framework loads and displays forms on the handheld device. The framework then receives actions from these forms back at the server – similar to a Web page. These forms are not coded, but are generated from xml files (also similar to Web pages). A form's xml file will be named **screen_<name>** and located in its own directory in the wireless project with the path `bin.generator.screens`.

EventHandler_<name> AbstractEventHandlers are generated along with the forms to receive actions. The EventHandler_<name> class extends the abstract class and actually implements the actions that can be received from the form. The EventHandler classes are coded by the developer to handle the logic for the handheld device.

<functional area>Utility Often, an EventHandler communicates with the rest of the SIM system by using logic available through a utility that covers common logic within a functional area.

EJB Service The EJBs to the regular SIM services are accessed from EventHandlers or Utilities by using the client-side EJB services (either by specifically instantiating or by using ClientServiceFactory).

Forms

Forms contain the page information that is sent back and forth to the actual device.

Event Handler

When a form is created, an AbstractEventHandler_<name>.java file must exist as well. The developer must then code an EventHandler_<name>.java file that matches the abstract handler. This section will outline how an EventHandler relates to a form and some of the general methods that are available to an EventHandler. [Example 1–23](#) is an example of a form designed in an .xml file for entering an item on an inventory adjustment:

Example 1–23 Screen_InventoryAdjustmentNormalItem

```
<Screen name="InventoryAdjustmentNormalItem">
  <LogicalScreen>
    <field name="itemId" type="string" length="21" />
    <field name="itemDesc" type="string" length="42" />
    <field name="reason" type="string" length="21" />
    <field name="unavailableLabel" type="string" length="10" />
    <field name="unavailableQty" type="string" length="5" />
    <field name="qtyLabel" type="string" length="15" />
    <field name="qty" type="string" length="5">1</field>
    <field name="uom" type="string" length="5" />
    <field name="packSize" type="string" length="5" />
  </LogicalScreen>
<PhysicalScreens deviceclass="dnw">
  <PhysicalScreen seq="0">
    <label y="0" x="0" height="1" width="21"
      style=".heading1">${wireless.inventoryAdjustment}</label>
```

```

        <label y="2" x="0" height="1" width="21" name="itemId"
field="itemId"></label>
        <label y="3" x="0" height="2" width="21" name="itemDesc"
field="itemDesc"></label>
        <label y="5" x="0" height="1" width="21" name="reason"
field="reason"></label>

        <label y="6" x="0" height="1" width="10" name="unavailableLabel"
field="unavailableLabel"></label>
        <label y="6" x="10" height="1" width="6" name="unavailableQty"
field="unavailableQty"></label>
        <label y="6" x="16" height="1" width="5" name="unavailableUnits" />

        <label y="8" x="0" height="1" width="9" name="qtyLabel"
field="qtyLabel"></label>
        <input y="8" x="10" height="1" width="6" name="qty" field="qty" seq="0"
acceptScan="false" validateKeyEventOnScan="false"/>
        <label y="8" x="16" height="1" width="5" name="uom" field="uom" />

        <label y="9" x="0" height="1" width="10" name="packSizeLabel" />
        <input y="9" x="10" height="1" width="6" name="packSize" field="packSize"
seq="1" acceptScan="false" validateKeyEventOnScan="false"/>

        <scan/>

        <cmdkey y="0" x="0" width="0" height="0" key="&toggle;" name="toggle"
action="callMethod" target="doToggle"/>
        <cmdkey y="0" x="0" width="0" height="0" key="&exit;" name="Exit"
action="callMethod" target="doExit" />
    </PhysicalScreen>
</PhysicalScreens>
</Screen>

```

The API of the `AbstractEventHandler` that was created to match the form is shown in the [Example 1-24](#):

Example 1-24 `AbstractEventHandler_InventoryAdjustmentNormalItem`

```

abstract public class AbstractEventHandler_InventoryAdjustmentNormalItem extends
SimEventHandler {
    abstract protected void onFormOpen();
    abstract protected void onFormClose();
    abstract public void onScan(String data);
    abstract public boolean qty_OnChange(String newValue);
    abstract public boolean qty_OnExit(String newValue);
    abstract public boolean packSize_OnChange(String newValue);
    abstract public boolean packSize_OnExit(String newValue);
    abstract public void doToggle();
    abstract public void doExit();
}

```

`OnFormOpen()` and `OnFormClose()` must exist for each `AbstractEventHandler` regardless of the form:

- `OnFormOpen()` is executed before the form is displayed to the handheld device. The code that populates the form with data should be placed in this method.
- `OnFormClose()` is executed when the form is removed from the handheld device.

The `onScan()` method matches the `<scan/>` tag in the xml, which indicated a row on the form into which to scan a value. When a value is scanned by the device, the information is passed to the `onScan()` method as a data parameter. The developer can implement this method in the `EventHandler` to process the scanned data (in this case, the barcode of an item).

Both `qty_OnChange()` and `qty_OnExit()` were created by the `<input>` tag with the `field=qty` set within that tag. Since `qty` was entered as the field, these two methods exist to handle processing when a quantity is entered.

Both `packSize_OnChange()` and `packSize_OnExit()` were created by the `<input>` tag with the `field =packSize` set within that tag. Since `packSize` was entered as the field, these two methods exist to handle processing when a pack size is entered.

The `doToggle()` method was created by the `<cmdkey>` tag based on the `target=value` section of the tag. Since `doToggle` was entered as the target value, this method was created. A `cmdkey` displays as an option on the screen. The method is executed in the `EventHandler` when the option is chosen on the screen. This is the same with the `doExit()` based on its `<cmdkey>` tag.

SimEventHandler

Each `AbstractEventHandler` extends from `SimEventHandler`, a superclass that contains methods for common tasks. These methods should always be used when these tasks must be performed. There are methods for the following:

- Assigning data to forms
- Reading data from forms
- Displaying alerts
- Displaying exceptions
- Checking locks
- Releasing locks
- Showing specialized screens (barcode, Yes/No choice, text input)
- Navigating to other forms

YesNoEventHandler

`YesNoEventHandlers` are simple choice windows that display a choice and allow the user to pick **Yes** or **No**.

Example 1–25 RequestCancelYesNoHandler

```
public class RequestCancelYesNoHandler extends SimYesNoHandler {
    public void performYes(IApplicationForm currentForm) throws Exception {
        try {
            ItemRequest itemRequest =
ItemRequestWirelessUtility.getContext().getItemRequest();
            if (itemRequest.getLineItems().size() > 0) {
                ItemRequestWirelessUtility.doSave(itemRequest, false);
            }
            currentForm.gotoForm(ItemRequestWirelessKeys.SCREEN_MENU);
        } catch (BusinessException be) {
            currentForm.gotoForm(ItemRequestWirelessKeys.SCREEN_MENU);
        } catch (Exception e) {
            handleException(e, currentForm);
        }
    }
}
```

```

    }
    public void performNo(IApplicationForm currentForm) throws Exception {
        try {
            currentForm.gotoForm(ItemRequestWirelessKeys.SCREEN_SUMMARY);
        } catch (Exception e) {
            handleException(e, currentForm);
        }
    }
    public String getTitle() throws Exception {
        return getText(ItemRequestWirelessUtility.getTitleKey());
    }
    public String getMessage() throws Exception {
        String id = ItemRequestWirelessUtility.getContext().getItemRequest().getId();
        return getMessage(ItemRequestWirelessKeys.MESSAGE_EXIT_CONFIRM, id);
    }
}

```

The `SimYesNoHandler` superclass that all `YesNoHandlers` should extend contains most of the same helper methods as the `SimEventHandler` class. This means that such functionality as translating text and handling exceptions should always use these helper methods.

The `SimYesNoHandler` also has the implemented code that returns the **Yes** and **No** choice labels for the screen, so the user only has to implement the following four methods for each new `YesNoHandler`:

- `performYes()` is executed when the user chooses the **Yes** option.
- `performNo()` is executed when the user chooses the **No** option.
- `getTitle()` returns the title to display at the top of the form.
- `getMessage()` return the query text to display on the form.

Wireless Context

A context represents a repository of data entered or being altered for a particular functional area within the user session. This context is carried in the repository to make it readily accessible between different forms. The `InventoryAdjustmentContext` is used as an example to trace some of the usages of context. Note that the context object itself simply has a set of data variables.

Example 1–26 *InventoryAdjustmentContext*

```

public class InventoryAdjustmentContext {
    private InventoryAdjustment inventoryAdjustment;
    private InventoryAdjustmentReason lastAdjustmentReason = null;
    private String lastScannedUIN = null;
    private Quantity scanEnteredQty = null;
    private Quantity computedQty = null;
    private boolean takeFromUnavailableBucket = false;
    private int currentUINIndex = 0;
    public InventoryAdjustment getInventoryAdjustment() {
        return inventoryAdjustment;
    }
    public void setInventoryAdjustment(InventoryAdjustment inventoryAdjustment)
    {
        this.inventoryAdjustment = inventoryAdjustment;
    }
    public boolean isTakeFromUnavailableBucket() {
        return takeFromUnavailableBucket;
    }
}

```

```

    }
    public void setTakeFromUnavailableBucket(boolean takeFromUnavailableBucket)
    {
        this.takeFromUnavailableBucket = takeFromUnavailableBucket;
    }
    // Other Getters & Setters
}

```

Access to the context is through the utility for the functional area, which contains a set of static helper methods to create, retrieve and remove the context. Note that the actual context itself is stored within the `SimWirelessRepository`.

Example 1–27 *InventoryAdjustmentWirelessUtility*

```

public static InventoryAdjustmentContext getContext() {
    return (InventoryAdjustmentContext)
        SimWirelessRepository.getValue(InvAdjustmentWirelessKeys.CONTEXT);
}

public static InventoryAdjustmentContext createContext() {
    InventoryAdjustmentContext context = new InventoryAdjustmentContext();
    SimWirelessRepository.setValue(InvAdjustmentWirelessKeys.CONTEXT, context);
    return context;
}

public static void removeContext() {
    SimWirelessRepository.removeValue(InvAdjustmentWirelessKeys.CONTEXT);
}

```

Wireless Utilities

Wireless Utilities are static classes that contain numerous helper methods to execute business logic, such as in the examples for context in which the context is created or retrieved, or in the following example where a new inventory adjustment was created. There is only one <name>WirelessUtility for each functional workflow on the handheld device.

The Wireless Utility contains public static helper methods to perform business logic for EventHandlers. Wireless Utilities do not contain any data variables at the class level as the utility does not store state of its data. That responsibility is handled by the context. [Example 1–28](#) code shows a utility method for persisting the inventory adjustment:

Example 1–28 *InventoryAdjustmentWirelessUtility*

```

public static void persistInventoryAdjustment(IApplicationForm currentForm) {
    InventoryAdjustment invAdjustment = getContext().getInventoryAdjustment();
    try {
        if (invAdjustment.isCoherent()) {
            ClientServiceFactory.getInventoryAdjustmentServices()
                .processInventoryAdjustment(invAdjustment);
            alert(currentForm, getTitleKey(), InvAdjustmentWirelessKeys.MESSAGE_
                ADJUSTMENT_COMPLETE,
                ItemWirelessKeys.SCREEN_SCAN_BARCODE, false);
        }
    } catch (BusinessException businessException) {
        String message = getMessage(businessException.getMessage(),
            businessException.getParameters());
    }
}

```

```

        alert(currentForm, getTitleKey(), message, getItemScreen(), true);
    } catch (Exception e) {
        handleException(e, currentForm);
    }
}

```

Form Paging

The `ScreenPageManager` and `PageableEventInterface` are used to create selection screens that go on for more than one visual screen worth of information on the handheld device. A **next** and **previous** command option exists on the base of the form to scroll through the pages.

The `ScreenPageManager` is a wireless framework class that handles a lot of the formatting and displaying of the options on a form and controls going forward and backward through the pages. Developers should never modify this class.

Primarily, developers access this information by having an `EventHandler` for a form implement the `PageableEventInterface`. The `ScreenPageManager` uses this defined API to control the paging.

Example 1–29 *PageableEventInterface*

```

public abstract Map getMenuItemMap();
public abstract String getScreenName();
public abstract IApplicationForm getCurrentForm();
public abstract String[] getPageFieldNames();
public abstract String[] getSpecialFieldValues();

```

The `ItemRequestSelectRequest` form displays a list of requests for the user to select from. These requests might not all fit on one form, so this `EventHandler` implemented the `PageableEventInterface`. In the implementation of `getMenuItemMap()`, a `Map` of `ItemRequests` is returned from the `Context` to be displayed as the list of options to select. The `getScreenName()` method returns the title of the screen.

Example 1–30 *EventHandler_ItemRequestSelectRequest*

```

public Map getMenuItemMap() {
    return (Map) SimWirelessRepository.getValue(ItemRequestWirelessKeys.ORDER_
MAP);
}
public String getScreenName() {
    return ItemRequestWirelessKeys.SCREEN_SELECT_REQUEST;
}

```

The method `getCurrentForm()` is implemented by `SimEventHandler`, so all `EventHandlers` automatically implement that method. The `getPageFieldNames()` method returns a list of names to assign to the options displayed on the screen. So in the following example, nine options (or item requests) are displayed with **order0** through **order9** assigned as their name:

Example 1–31 *EventHandler_ItemRequestSelectRequest*

```

private static final String[] orderFieldNames = { "order0", "order1", "order2",
"order3", "order4", "order5", "order6", "order7", "order8", "order9" };

public String[] getPageFieldNames() {
    return orderFieldNames;
}

```

```

public String[] getSpecialFieldValues() {
    return null;
}

```

When the option is selected, the Wavelink framework calls back to a method named after the options names assigned in `getPageFieldNames()`. In this case, `selectOrder0()`, `selectOrder1()`, and so on. This is where the developer can place code to handle the selection. There are no examples of `getSpecialFieldValues()`. This method returns null in all `EventHandlers` that implement the interface.

Example 1–32 *EventHandler_ItemRequestSelectRequest*

```

public void selectOrder0() {
    selectOrder(0);
}
public void selectOrder1() {
    selectOrder(1);
}
// Rest of orderFieldNames...public void selectOrder9() {
    selectOrder(9);
}

```

Once the methods are defined, starting the page display is easy. In the `onFormOpen()` method, if there is a list available to display selections for, then retrieve the page manager and call `initializeScreen()`. This sets up and displays the first page of selection options. It should be the last method executed in `onFormOpen()`:

Example 1–33 *EventHandler_ItemRequestSelectRequest*

```

protected void onFormOpen() {
    try {
        LogService.debug(this, getClass().getSimpleName() + ".onFormOpen()");
        setFormText(FIELD_INSTRUCTIONS, getLabel("Select Item Request"));
        if (getMenuItemMap() == null || getPageManager() == null) {
            initializeOnEntry();
        } else {
            getPageManager().initializeScreen();
        }
    } catch (Exception e) {
        handleException(e);
    }
}

```

Customizing Wireless Forms

This section contains some tips on customizing wireless code. Customizing wireless code requires modifying source code in SIM. This needs to be handled with care.

Coding Guidelines

- The wireless clients should always access services through the `ClientServiceFactory` class.
- Do not alter existing context classes. Create new ones instead and store in `SimWirelessRepository`.
- When at all possible, design the modifications to be new forms or replacements to current forms instead of modifying current forms.
- Similar to forms/screens, attempt to write new utility classes rather than modifying current ones.

By following the guidelines above, the only code that should need to be modified in SIM is the code that directs one form to a newly designed form – keeping the amount of rework at a minimum for future releases.

Creating a New Context

If you need to store additional state data during a session, create an entirely new context to store the information. The newly created context must then be placed in the `SimWirelessRepository`. Next, create a custom wireless utility to handle interaction with the context, including placing the context in the `SimWirelessRepository`.

```
public class MyCustomContext() {
    { . . . . } // Context code.
}
```

Creating a New Utility

If new functionality is desired in the wireless application that needs to access a new context or access new services, then the developer should create an entirely new utility to use from the eventhandlers to execute this code.

If you need ready access to a utility method or need to override the functionality of a utility method, then subclass the utility in question with your new utility as shown in [Example 1-34](#):

Example 1-34 *MyCustomUtility*

```
public class MyCustomStockCountUtility extends StockCountWirelessUtility {
    public static MyCustomContext getContext() {
        return (MyCustomContext)
        SimWirelessRepository.getValue(MyCustomContextKeys.CONTEXT);
    }
    public static MyCustomContext createContext() {
        MyCustomContext context = new MyCustomContext ();
        SimWirelessRepository.setValue(MyCustomContextKeys.CONTEXT, context);
        return context;
    }
    public static void removeContext() {
        SimWirelessRepository.removeValue(MyCustomContextKeys.CONTEXT);
    }
    [ . . . . ] // New Utility Code
}
```

Altering Code in an EventHandler

Because of the manner that the Wavelink code functions, eventhandlers cannot be easily replaced or sub-classed. Instead, the eventhandler must be removed from the JAR, re-coded, and placed in a custom JAR earlier in the classpath. These modifications are not guaranteed to function correctly with newer releases.

Altering Code in a Form

Altering a Wavelink form is a complicated process:

1. Alter the form_<name> source code.
2. Alter the form_dnw_<name> source code.
3. Alter the AbstractEventHandler_<name> source code.
4. Alter the EventHandler_<name> source code.

All of these files must be placed back in the custom JAR that is first in the classpath.

Significant Classes to Understand

Before attempting to modify or create new handheld Wavelink forms, read all documentation supplied by Wavelink. The following is a list of critical framework classes:

- CommandListHelper
- CommandListInterface
- InputTextInterface
- LocaleWirelessUtility
- PageableEventInterface
- PrintSelectInterface
- ScreenPageManager
- SimBasicHandler
- SimEventHandler
- SimWirelessRepository
- SimYesNoHandler
- WirelessExceptionManager
- WirelessPrintService
- WirelessUtility
- WirelessValidation
- YesNoEventInterface

Exceptions and Logging

This section covers exceptions and logging in SIM so that if code is customized, the exception handling framework can be utilized.

Exceptions

SimServerException

The SimServerException class represents an exception originating on the server. It contains an ID counter and a timestamp field. This ID counter starts at one (1) and increases until the server is restarted or the maximum integer value is reached and then it resets to one (1) again. The ID is used to uniquely identify an exception within a server log. This class can be instantiated around another exception, such as an SQLException.

DowntimeException

A DowntimeException occurs on the client when communication to the server fails or a severe problem on the server takes place.

BusinessException

This type of execution is thrown from either the client or server whenever the code encounters an attempt to perform some action that is defined as invalid by the functional business requirements. Rules and business objects primarily throw BusinessExceptions. BusinessExceptions are not considered severe errors and allow the system to continue to operate after the exception takes place.

UIException

A UIException is used strictly on the client and indicates a failure in the GUI framework or a general failure in UI processing.

Exception Handling

The DAO Layer

All DAO interfaces should throw SimServerException. These exceptions should not be logged in the DAO layer. This is handled by the EJB before propagating the exception to the client. The database framework generates most SimServerExceptions, though sometimes logic requires manually throwing a SimServerException. [Example 1–35](#) is an example of a DAO interface declaration and a SimServerException thrown manually:

Example 1–35 ProductGroupDao

```
void insert(ProductGroup productGroup) throws SimServerException;
```

Example 1–36 ProductGroupOracleDao

```
public void insert(ProductGroup productGroup) throws SimServerException {
    if (productGroup.getId() != null) {
        throw new SimServerException("Unable to insert product group with an existing
identifier!");
    }
    productGroup.doSetId(getNextGroupId());
    execute(new ParametricStatement(RkProductGroupDataBean.INSERT_SQL,
        fromObjectToBean(productGroup).toList(true)));
    if (productGroup.isAllItems()) {
        return;
    }
    insertProductGroupDetails(productGroup);
}
```

The Service Layer

The service layer framework is written so that Exception, SimServerException, BusinessException and DowntimeException are all thrown by the service and the EJB, such that the exception is not wrapped when it arrives at the client. Services should all be declared to throw a simple Exception. No logging needs to be handled manually in the code. The framework code handles logging the exceptions before throwing them to the client. The following is an example of a service declaration and a BusinessException thrown manually from within the service layer. DowntimeExceptions are generally only thrown when an unexpected Throwable is caught from the code (such as a NullPointerException) or the EJB stub is no longer communicating.

Example 1–37 ReplenishmentServerServices

```
public PickList updatePickList(PickList pickList) throws Exception {
    PickListUpdateCommand command = CommandFactory.createPickListUpdateCommand();
    command.setPickList(pickList);
    command.execute();
    return command.getPickList();
}
```

Example 1–38 PickListUpdateCommand

```
protected void doExecute() throws Exception {
    PickList dbPickList =
    DAOFactory.getPickListDao().selectPickList(pickList.getId());
    if (dbPickList == null) {
        throw new BusinessException(ErrorKey.PICK_LIST_LIST_MUST_EXIST);
    }
    if (dbPickList.getStatus() == PickListStatus.CANCELED) {
        throw new BusinessException(ErrorKey.PICK_LIST_CANCELLED_ERROR);
    }
    if (dbPickList.getStatus() == PickListStatus.CLOSED) {
        throw new BusinessException(ErrorKey.PICK_LIST_CLOSED_ERROR);
    }
    // Rest Of Method
}
```

The UI Layer

On the client side, it is preferable that a `BusinessException` be thrown whenever business logic reaches an error state. All exceptions are caught and handled by the framework.

Throwing an Exception

When throwing an exception within the PC application, throw a `BusinessException` with the appropriate message. The exception should always be propagated to the last place that handled an event in order to cleanly break the execution flow.

Example 1–39 ItemTicketListModel

```
public void updateStockOnHand(ItemTicket itemTicket) throws Exception {
    Quantity stockOnHand = itemTicket.getItem().getAvailableStockOnHand();
    if (stockOnHand.intValue() < 1) {
        throw new BusinessException(SimClientErrorKey.ITEM_NOT_UPDATED);
    }
    // Remainder of Method
}
```

Catching an Exception

Exceptions should always be propagated and caught at the screen layer if triggered by a menu button, or in the panel layer if triggered by an editor event. The helper method `displayException()` should always be used to handle the error correctly, whether in a screen or panel. The following example allows each of the panel `handle()` methods to simply throw an exception and allows the screen to handle it.

Example 1–40 ItemTicketListScreen

```

public void navigationEvent(NavigationEvent event) {
    String command = event.getCommand();
    try {
        if (command.equals(SimNavigation.PRINT_TICKETS)) {
            panel.handlePrintTickets();
        } else if (command.equals(SimNavigation.CREATE)) {
            panel.handleCreate();
        } else if (command.equals(SimNavigation.UPDATE_SOH)) {
            panel.handleUpdateStockOnHand();
        } else if (command.equals(SimNavigation.DELETE)) {
            panel.handleDelete();
        }
    } catch (Throwable exception) {
        displayException(panel, event, exception);
    }
}

```

An alternate case to handling exceptions at the screen layer occurs when the code must continue to execute normally after the exception is displayed, usually to clean up or reset some information. In [Example 1–41](#), the table must be refreshed whether or not an error occurred:

Example 1–41 ItemTicketListPanel


```

public void handleUpdateStockOnHand() throws Exception {
    if (itemTicketTable.getSelectedRowCount() == 0) {
        displayError(SimClientErrorKey.NO_ROWS_SELECTED);
        return;
    }
    // Code removed from example
    List<ItemTicketWrapper> wrappers = itemTicketTable.getAllSelectedRowData();
    for (ItemTicketWrapper wrapper : wrappers) {
        try {
            model.updateStockOnHand(wrapper.getItemTicket());
        } catch (BusinessException exception) {
            displayException(exception);
        }
    }
    itemTicketTable.refreshTable();
}

```


Processing an Exception

BusinessExceptions and UIExceptions are caught and their message displayed in a pop-up window that locks the application as shown in [Figure 1–2](#). When the window is exited, control should be returned to the screen/area in which the error occurred. If the UIException has an ErrorSeverity of FATAL, then a Fatal Window is displayed and the user is returned to the main login screen of the application.

Figure 1–2 Table Editor Error Screen

SimServerExceptions are thrown from the server layer and regardless of the details of the exception, only one message displays as shown in [Figure 1–3](#).

It includes an error number and the date and time that the error occurred. This can be used to find the error in the server exception log. Click **Details** to display the contents of the main exception.

Figure 1–3 Severe Error Screen

Logging

Logging allows the developer to write information about errors or processes to a file. Errors on the server side are automatically logged by the EJB class regardless of whether or not they come from the DAO layer or business layer. Therefore, errors that are logged in local code end up being logged twice if the user logs them.

LogService

If it is necessary to log an error in the business layer or DAO layer, this is done through the LogService class, which provides numerous static methods that hide the implementation away from the end developer. The SimStore business object in the example below logs a message if it fails to load the buddy stores.

Note: Certain API such as Java Open Transaction Manager (JOTM) use Apache Log4J as their default logging. Therefore, Log4J will also need to be configured.

Example 1–42 SimStore

```
private void doLoadStoreLists() {
    if (storesNotLoaded) {
        try {
            StoreServices storeServices = ClientServiceFactory.getStoreServices();
            buddyStores
                =
                CollectionUtil.newSortedSet(storeServices.findBuddyStores(store.getId()));
            autoReceiveStores
                =
                CollectionUtil.newSortedSet(storeServices.findAutoReceiveStores(store.getId()));
            storesNotLoaded = false;
        } catch (Exception exception) {
            LogService.error(this, "SimStore could not load store lists",
exception);
        }
    }
}
```

Debugging

LogService provides the ability to log messages at the info, debug and warn level as well. All debugging messages should be logged through LogService as well. In [Example 1–43](#), the e-mail dispatcher logs a warning if no permission is associated with the e-mail.

Example 1–43 EmailDispatcher

```
public static void sendEmailAlert(EmailAlert emailAlert) {
    String fromAddress = RkConfigManager.getString(RkConfigManager.EMAIL_FROM_NAME);
    if (StringHelper.isNullOrEmpty(fromAddress)) {
        LogService.error("EmailDispatcher", "Invalid email from-address");
        return;
    }
    String permissionName = emailAlert.getPermissionName();
    if (StringHelper.isNullOrEmpty(permissionName)) {
        LogService.warn("EmailDispatcher", "Email alert is not associated to a
permission.");
        return;
    }
    // Remainder Of The Code
}
```

The business rule executed when the logic attempts to create a new line item for a return will log a debug level message if the item is not supplied by the correct source.

Example 1–44 ReturnCreateLineItemRule

```
public static void execute(Return stockReturn, StockItem stockItem) throws
BusinessException {
    Source source = stockReturn.getDestination();
    if (source == null) {
        throw new BusinessException(ErrorKey.RETURN_NO_DESTINATION);
    }
    if (stockReturn.isVendorReturn()) {
        try {
            ItemServices services = ClientServiceFactory.getItemServices();
            if (services.isItemSuppliedBySupplier(stockItem.getId(), source.getId()))
{
                return;
            }
        }
    }
}
```

```

    } catch (Throwable exception) {
        LogService.debug(ReturnCreateLineItemRule.class, "Failed rule.",
exception);
    }
    throw new BusinessException(ErrorKey.RETURN_NO_SOURCE);
}
// Remainder of rule code
}

```

Logs

One of the first places to look for information concerning a problem in SIM is in the log files. Stack traces and debugging information can be found within the log files. The log files are configured to roll over once they reach a certain size (currently 10 MB). Once a log file reaches the configured size, it is renamed (for example, `sim.log` will be renamed to **sim.log.1**) and new log messages are written to a new file (for example, `sim.log`). If there are already rolled-over logs, they are also be renamed (for example, `sim.log.1` becomes `sim.log.2`, `sim.log.2` becomes `sim.log.3`, and so forth). Only ten files are kept. If ten files already exist and the current file rolls over, the oldest log file is deleted.

Client Side Logs

On the client, logs are sent to the console and to the file `<location of sim client>\bin\log\sim.log`.

Logging is configured in `client/resources/log4j.xml`. This file defines which kinds of messages are logged and where they are logged.

Server Side Logs

On the server, logs are saved to `<location of server>\bin\log\sim.log`. Log messages are also displayed in the console.

Exception Format

The following example demonstrates a formatted and logged service exception. The first line contains the EJB and method name of the exception failure. The second line contains ERROR with an ID (in this case 1). This ID is displayed on the client side for reference. It is followed by the user ID of the transaction user, a timestamp, the type of exception, the primary message, and the primary message of the root cause. Following that is the stack trace of the exception.

```

ERROR 02:14:05.728 [ejb.ItemEjb] findItemVOs: Exception occurred during service
invocation <
ERROR-1 User: 15000 Time: 11/27/06 2:14 PM Type: ApplicationException Message:
This is an example exception. Root Cause: Application is in illegal state.>
oracle.retail.sim.closed.common.ApplicationException: This is an example
exception. at
oracle.retail.sim.closed.item.ItemServerServices.findItemVOs(ItemServerServices.ja
va:37) at
oracle.retail.sim.closed.item.ItemHelper.findItemVOs(ItemHelper.java:55) at
oracle.retail.sim.closed.item.ejb.ItemEjb.findItemVOs(ItemEjb.java:127) at
sun.reflect.NativeMethodAccessorImpl.invoke0(Native Method) at
sun.reflect.NativeMethodAccessorImpl.invoke(NativeMethodAccessorImpl.java:39) at
sun.reflect.DelegatingMethodAccessorImpl.invoke(DelegatingMethodAccessorImpl.java:
25) at
java.lang.reflect.Method.invoke(Method.java:585) at
com.evermind.server.ejb.interceptor.joinpoint.EJBJoinPointImpl.invoke(EJBJoinPoint
Impl.java:35) at

```

```

com.evermind.server.ejb.interceptor.InvocationContextImpl.proceed(InvocationContextImpl.java:69) at
com.evermind.server.ejb.interceptor.system.DMSInterceptor.invoke(DMSInterceptor.java:52) at
com.evermind.server.ejb.interceptor.InvocationContextImpl.proceed(InvocationContextImpl.java:69) at
com.evermind.server.ejb.interceptor.system.TxSupportsInterceptor.invoke(TxSupportsInterceptor.java:37) at
com.evermind.server.ejb.interceptor.InvocationContextImpl.proceed(InvocationContextImpl.java:69) at
com.evermind.server.ejb.interceptor.system.DMSInterceptor.invoke(DMSInterceptor.java:52) at
com.evermind.server.ejb.interceptor.InvocationContextImpl.proceed(InvocationContextImpl.java:69) at com.evermind.server.ejb.StatelessSessionEJBObject.OC4J_
invokeMethod(StatelessSessionEJBObject.java:86) at ... 24 more

```

Modifying Data Transport to External Systems

We can continue the previous example of Generic Retailers Inc, adding the new attribute Season to the items within the system. Besides the SIM side as given in earlier examples, this information could also arrive from an external system and might need to be sent to external systems. So in this case, the following steps are taken to support the new data:

1. Update DEOs
2. Update Injectors
3. Update Consumers
4. Update Stagers
5. Update Publishers

This customization document does not cover any modifications to code or processes external to SIM, or in other words, how to update the external system. As such, this document does not cover updating RIB configurations and payloads should the external system be linked using the RIB.

Process of Receiving an External Message

Do the following to receive an external message:

1. The external message is received by an Injector.
2. The Injector class converts the message to a Data Exchange Object.
3. The Data Exchange Object (DEO) is written into the STAGED_MESSAGE table.
4. The Data Exchange Object (DEO) is read from the STAGED_MESSAGE table by a polling timer and given to a Consumer object to be processed.
5. The Consumer object uses the DEO to do processing and update SIM information.

Process of Sending an External Message

Do the following to send an external message:

1. Business processes use a Stager class to convert business data into a DEO.
2. The DEO is written into the STAGED_MESSAGE table.

3. The DEO is read from the STAGED_MESSAGE table by a polling timer and given to a Publisher object to be processed.
4. The Publisher object converts the DEO to external information and sends the information to an external system.

Update DEOs

The first step of customizing the external message process is to update the Data Exchange Objects (DEOs) to contain the added attributes. ItemHdrDEO (incoming message containing the basic item information) and ReturnToVendorLineItemDEO (outgoing message containing item information on a return) will be used as examples of this process.

Since this is new information on already existing messages, the original DEOs should be sub-classed and the new attributes added much the same way as was done for business objects and value objects:

```
public class GriItemHdrDEO extends ItemHdrDEO {
    private String season;
    public GriItemHdrDEO() {
        super();
    }
    public String getSeason() {
        return season;
    }
    public void setSeason(String season) {
        this.season = season;
    }
}
```

DEOs are instantiated through a DEOFactory. This factory uses a configured implementation to create the objects. The next step is to subclass the default implementation (DEOFactoryImpl) to override the methods that create the modified DEOs:

```
public class GriDEOFactoryImpl extends DEOFactoryImpl {
    public ItemHdrDEO createItemHdrDEO() {
        return new GriItemHdrDEO();
    }
    public ReturnToVendorLineItemDEO createReturnToVendorLineItemDEO() {
        return new GriReturnToVendorLineItemDEO();
    }
}
```

To configure the factory, simply modify common.cfg with the classpath of your new code:

```
DEO_FACTORY_IMPL=gri.custom.code.GriDEOFactoryImpl
```

Update Injectors

To update the payload-to-DEO injection mapping in SIM, a developer must extract the actual source code for SIMMessageMapperUtil, then modify the original source code, re-jar the correct project and re-sign everything for deployment. This process should be left up to a system administrator.

The `SIMMessageMapperUtil` is the class responsible for mapping payloads to DEOs. Find the appropriate `map()` method and alter the contents of the method:

```
private static ItemHdrDEO convert(ItemHdrDesc itemHdrDesc) {
    ItemHdrDEO itemHdrDEO = DEOFactory.createItemHdrDEO();
    itemHdrDEO.setItemId(itemHdrDesc.getItem());
    //..... remaining original code
    itemHdrDEO.setDefaultWastePercent(itemHdrDesc.getDefaultWastePct());
    itemHdrDEO.setSeason(itemHdrDesc.getSeason());
    // New Attribute
    return itemHdrDEO;
}
```

Update Consumers

The first step of customizing a consumer is to subclass the consumer and add custom logic. In order to deal with the new season attribute, `ItemCreateConsumer` is customized as an example. Every consumer must implement `consume()`, and so this is the method that must be overridden with custom code. Calling `super.consume()` will guarantee that the normal process of consuming external data will be executed and that future releases will continue to work with no code changes.

```
public class GriItemCreateConsumer extends ItemCreateConsumer {
    public void consume(List<DataExchangeObject> deos) throws Exception {
        super.consume(deos);

        GriItemDao griItemDao = new GriItemDao();
        for (DataExchangeObject deo : deos) {
            ItemHdrDEO itemHdrDEO = ((ItemDEO) deo).getItemHdrDEO();
            griItemDao.updateSeason(itemHdrDEO.getItemId(), itemHdrDEO.getSeason());
        }
    }
}
```

The second step is very similar to other customization patterns: the factory implementation is altered to return the custom consumer and then `sim.cfg` is updated to point at the new implementation. The custom consumer factory implementation should extend the regular factory implementation and then override the `getConsumer()` method. After first returning any customized consumers, it can then call the superclass to retrieve a SIM supplied consumer:

```
public class GriMessageComsumerFactoryImpl extends SimMessageComsumerFactoryImpl {
    public SimMessageConsumer getConsumer(SimMessageType messageType) throws
Exception {
        if (messageType == SimMessageType.ITEM_CRE) {
            return new GriItemCreateConsumer();
        }
        return super.getConsumer(messageType);
    }
}
```

To configure the factory, modify `sim.cfg` with the classpath of your new code:

```
MESSAGE_CONSUMER_FACTORY_IMPL=gri.customer.code.GriMessageConsumerFactoryImpl
```

Update Stagers

Stagers and Publishers are the opposite of Consumers and Injectors. They take data into SIM and prepare it to be sent externally. Using our example of `ReturnToVendorLineItemDEO`, customization begins with modifying the Stager that deals with staging vendor returns. To do this, a developer must extract the actual source code for `VendorReturnStager`, then modify the original source code, re-jar the correct project and re-sign everything for deployment. This process should be performed by a system administrator/developer.

Update Publishers

To update the DEO-to-Payload publisher mapping in SIM, a developer must extract the actual source code for `SIMMessageMapperUtil`, then modify the original source code, re-jar the correct project and re-sign everything for deployment. This process should be performed by a system administrator/developer.

The `SIMMessageMapperUtil` is the class responsible for mapping DEOs to payloads or other external messages. Find the appropriate `map()` method and alter the contents of the method.

```
private static void setLineItems(RTVDesc payload, List<ReturnToVendorLineItemDEO>
lineItems) {
    for (ReturnToVendorLineItemDEO lineItem : lineItems) {
        RTVDtl payloadDtl = new RTVDtl();
        payloadDtl.setItemId(lineItem.getItemId());
        payloadDtl.setUnitQty(lineItem.getUnitQty());
        payloadDtl.setFromDisposition(SimArtsConstants.DISPOSITION_TYPE_AVAILABLE);
        payloadDtl.setToDisposition("");
        payloadDtl.setReason(lineItem.getReturnReason());
        payloadDtl.setCustomAttribute(lineItem.getCustomAttribute());
        payload.getRTVDtl().add(payloadDtl);
    }
}
```

Modifying Source Code

Customizing the data transport to external systems currently still requires modifying SIM's source code. To build and deploy source modifications correctly, make a separate project for custom-modified code. Make sure any existing source code files that are going to be altered have the exact same classpath as in the base code. Build a custom JAR with the modified code. This custom JAR should be placed first in the execution classpath so that classes found within the JAR are chosen by the JVM rather than the base classes. This will require un-signing and re-signing all the JARs in the SIM-client application, since all JARs must be signed with the same signature for Web Start to work correctly. Consult the `jarsigner` documentation from Sun for further information on the JAR un-signing/signing process.

The SIM application is based on a style of code that includes a clear separation of closed and shared concepts. The code that resides in packages that contain **closed** in their classpath is considered essential to the integrity of the product and is not released.

Note: This closed source code should never be modified under any circumstances. Any changes to closed source code will likely make the system unusable and not upgradeable.

Source code that resides in the classpath that contains **shared** in its structure can be modified to accommodate altered functionality. All care should be given to read the appropriate documentation before modifying the code.

Note: Customized source code must be manually integrated during future releases of the product.

Customizing Look and Feel

Customization of the look and feel of the SIM PC application is available directly through the PC GUI and the appropriate privileges. Fonts, colors and icons can be changed to suit the company's desires. Completely new and fresh themes can be created directly through SIM. Refer to the *Oracle Retail Store Inventory Management User Guide* for description of how to use these features.

Visual appearances outside of this spectrum, such as widget shapes or animation, are not open to customization. Note that if completely new workflows are built on the PC, there are no restrictions as to what UI elements are put on the new screens.

The handheld code is not open to look and feel changes. These devices use simple two-tone text-based screens. All customizations are subject to the frameworks provided by Wavelink. See the Wavelink documentation for additional information.

Customizing Barcodes

Barcodes are handled in SIM by barcode processors. The first step of customization is to understand the `BARCODE_PROCESSOR` table in the database. This table is read to determine which barcode processors should be used when searching for items based on an input string.

Table 1–12 *BARCODE_PROCESSOR*

Column Name	Data Type	Nullable	Description
NAME	VARCHAR2(25)	No	The name of the format processor.
DESCRIPTION	VARCHAR2(256)	Yes	The description of the format processor.
FILE_NAME	VARCHAR2(256)	No	The full classpath Java class name of the processor.
ACTIVE	VARCHAR2(1)	No	Y indicates it is active and N indicates it is not active.

The `NAME` and `DESCRIPTION` rows are not used and are simply there to label the record in the database.

The `FILE_NAME` row represents the fully qualified classpath to the .java file that implements that particular barcode. For example, the UPC-E barcode processor `FILE_NAME` value supplied by SIM is `oracle.retail.sim.closed.item.barcode.BarcodeProcessorUPCE`.

The ACTIVE row must have a Y or N value to determine whether or not it is used in the system. The first and easiest customization is to activate or deactivate barcode processors based on usage. SIM provides several barcode processors which are all marked as **Active** by default. Updating the ACTIVE column to N for those not used saves processing time.

To add new barcode processors to the system, first code a new barcode processor Java class and then insert a row into the BARCODE_PROCESSOR table like in [Table 1-13](#). This example is the processor for a 24-character barcode. The Java class must be placed in the classpath of the deployed server.

Table 1-13 *BARCODE_PROCESSOR*

Column Name	Data Type	Nullable	Description
NAME	VARCHAR2(25)	No	UPC-24
DESCRIPTION	VARCHAR2(256)	Yes	24 character barcode processor
FILE_NAME	VARCHAR2(256)	No	custom.barcode.BarcodeProcessorUPC24
ACTIVE	VARCHAR2(1)	No	Y

Creating a Barcode Processor

Every barcode processor must implement the BarcodeProcessor interface:

```
public class BarcodeProcessorUPCE implements BarcodeProcessor
```

There are several methods defined by the interface. The purpose of each of these methods is outlined in the following list. Implement the logic of each method to satisfy the requirements of the barcode.

- Method: `boolean isPossibleFormatMatch(String barcode)`
This method must return **true** if it is possible that the barcode be a match to this barcode processor format; **false** if it does not.
- Method: `boolean isType2Format();`
This method must return **true** if the barcode processor is for a type 2 barcode; **false** otherwise.
- Method: `String getItemId(String barcode);`
This method must parse the item identifier out of the barcode and return this value.
- Method: `int getPrefix(String barcode)`
The method must return a known prefix to the barcode assuming that the barcode has a standardized prefix (for example, all Type 2 barcodes start with 2). Return -1 if no standard prefix exists.
- Method: `String getFormatCode();`
Returns the format code for the barcode format. This format code is the value that must be assigned to the item in the AS_ITM table in the BARCODE_FORMAT column.
- Method: `Boolean isPriceSupported();`
Return **true** if the barcode contains a price value; **false** otherwise.

- Method: `String getPrice(String barcode);`

Returns the price portion of the barcode, or null if no price exists in barcode.

A full example of the `BarcodeProcessorUPC24`:

```
public class BarcodeProcessorUPCE implements BarcodeProcessor {
    protected int totalLength = 24;
    protected String formatCode = "UPC24";
    public boolean isPossibleFormatMatch(String barcode) {
        if (barcode == null) {
            return false;
        }
        return (barcode.length() == totalLength);
    }
    public boolean isType2Format() {
        return false;
    }
    public String getItemId(String barcode) {
        return barcode.substring(3, 14);
    }
    public int getPrefix(String barcode) {
        return -1;
    }
    public String getFormatCode() {
        return formatCode;
    }
    public boolean isPriceSupported() {
        return true;
    }
    public String getPrice(String barcode) {
        return barcode.substring(16, 22);
    }
}
```

Customizing E-mail Alerts

This section covers e-mail alerts within SIM and how to customize their content.

The E-mail Server Configuration

The e-mail server is determined through the property `MAIL_JNDI_NAME` in `server.cfg` configuration file. The value for this property determines the session name on the server that should be used. The following variable is the default property:

```
MAIL_JNDI_NAME=mail/SimMailSession
```

This jndi name is used to retrieve a `Session` from the server from which we can get a `Transport` object and send a `MimeMessage` object, the fundamental classes of sending e-mails. See "[E-mail Server Class Definitions](#)" for further explanation.

The actual mail server associated with `mail/SimMailSession` is assigned to the server during the build and deploy. The install configuration templates include an input value for this `input.mail.host` that is populated when the template is loaded by looking in the specific properties files, so the `ant.install.properties` should contain a value for `input.mail.host` such as the following:

```
## Properties from Page:MailSessionDetails
input.mail.host = sysserver01
```

E-mail Server Class Definitions

The following is the standard javax package classes that are used as part of the e-mail alert system. For more information, access the documentation for the current version of Java used in the system.

javax.mail.Session

The Session class represents a mail session and is not sub-classed. It collects together properties and defaults used by the mail APIs. A single default session can be shared by multiple applications on the desktop. Unshared sessions can also be created. The Session class provides access to the protocol providers that implement the Store, Transport, and related classes. The protocol providers are configured using the following files:

- javamail.providers and javamail.default.providers
- javamail.address.map and javamail.default.address.map

javax.mail.Transport

An abstract class that models a message transport. Subclasses provide actual implementations. Note that Transport extends the Service class, which provides many common methods for naming transports, connecting to transports, and listening to connection events.

javax.mail.Message

This class models an e-mail message. This is an abstract class. Subclasses provide actual implementations. Message implements the Part interface. Message contains a set of attributes and content. Messages within a folder also have a set of flags that describe its state within the folder.

javax.mail.internet.MimeMessage

This class represents a MIME-style e-mail message. It implements the Message abstract class and the MimePart interface. Clients wanting to create new MIME-style messages instantiate an empty MimeMessage object and then fill it with appropriate attributes and content. This is the type of mail message that SIM uses.

SIM E-mail System Configuration Values

The following is the list of system configuration values that can be selected or entered for SIM. This can be done through the system administration area of the client application.

EMAIL_FROM_NAME

When the system sends e-mail alerts, this is the e-mail address that is displayed in the **from** area of the e-mail.

TRANSFER_DAMAGED_EMAIL_ALERT

If set to **yes**, sends an e-mail alert when the receiving store receives goods as damaged.

TRANSFER_DISPATCH_EMAIL_ALERT

If set to **yes**, sends an e-mail alert when the sending store dispatches a transfer.

TRANSFER_OVER_UNDER_EMAIL_ALERT

If set to **yes**, sends an e-mail alert when the receiving store received under/over the transferred quantity.

TRANSFER_REQUEST_APPROVE_EMAIL_ALERT

If set to **yes**, sends an e-mail alert when the transfer request has been approved by the sending store.

TRANSFER_REQUEST_REJECT_EMAIL_ALERT

If set to **yes**, sends an e-mail alert when the transfer request has been rejected by the sending store.

DAYS_TO_HOLD_DISPATCHED_TRANSFER_BEFORE_SENDING_EMAIL_ALERT

The number of days before an e-mail alert about a dispatched transfer is sent.

DAYS_TO_SEND_EMAIL_ALERT_BEFORE_NOT_AFTER_DATE_FOR_RETURN_REQUESTS

Returns requests generated in an external system sometimes require the return to be dispatched to the warehouse before a certain date. This option prompts the recipient of the e-mail the specified number of days before the not-after-date is reached if the return was not dispatched.

SIM E-mail Batch Jobs

There are two batch jobs that can be run that produce e-mail alerts in the system:

TransfersOverdueBatchJob

Batch job that finds dispatched transfers that have not been received and then generates/sends an e-mail to users whom have correct permissions. The alert is only sent if the number of days specified in the Days To Hold Dispatched Transfer Before Alert system configuration option has been exceeded.

ReturnNotAfterDateAlertJob

Batch job that generates and sends e-mail alerts for any Requested or Pending returns with a not-after-date coming up within the number of days specified in the Days To Send Email Alert Before Not After Date Return Requests system configuration option.

SIM-Developed Classes Involved

The following is a brief summary of the SIM-developed Java classes used in the e-mail alert process:

EmailDispatcher.java

This class is responsible for sending e-mail alerts. It validates users and permissions to determine who gets e-mailed and performs the actual sending of the e-mail.

EmailAlert.java

This interface is implemented by all e-mail alert commands. It contains the method APIs necessary for the e-mail framework classes to perform generic processes on e-mail alerts.

EmailAlertCommand

EmailAlertCommands are the java classes that construct the content of the e-mail to send to the users. This is the superclass of all e-mail commands that follows the command pattern and implements the EmailAlert interface. Each sub-class of this class must implement the interface methods of EmailAlert.

ReturnRequestEmailAlertCommand

This command builds the e-mail that notifies users when an active Return is nearing its not-after-date.

TransferDamageEmailAlertCommand

This command builds the e-mail that notifies users when items have been received as damaged.

TransferDispatchRequestEmailAlertCommand

This command builds the e-mail that notifies users when a transfer has been requested.

TransferDispatchedEmailAlertCommand

This command builds the e-mail that notifies users when a transfer has been dispatched.

TransferDispatchedOverdueEmailAlertCommand

This command builds the e-mail that notifies users when a dispatched transfer is overdue.

TransferOverUnderReceiptEmailAlertCommand

This command builds the e-mail that notifies users when a transfer is received with quantities that are different than the amount transferred.

UINStoreAlteredEmailAlertCommand

This command builds the e-mail that notifies users that a UIN has had its store location moved without going through a normal inventory transaction.

UserPasswordAssignmentEmailAlertCommand

This command builds the e-mail that notifies a user when the system has assigned a new password to their account.

Customizing an E-mail

The first step of customizing an e-mail alert is to subclass SIM's e-mail alert and add custom logic. The `TransferDamageEmailAlertCommand` is customized as an example. The easiest way to accomplish this is to sub-class the original command. Every e-mail alert must implement the `EmailAlert` interface. The interface consists of the following for methods. Customization will only require altering the `createSubjectLine()` and `createEmailContent()` method:

- Method: `String getPermissionName();`
This returns the name of the permission required to receive this e-mail from the system.
- Method: `Long getDestinationId();`
This method returns the store identifier of the store to receive the e-mail.
- Method: `String createSubjectLine(Locale locale);`
Returns the subject line of the e-mail. Locale might be used to internationalize the e-mail subject line.
- Method: `String createEmailContent (Locale locale);`
Returns the content of the e-mail message. Locale may be used to internationalize the e-mail content.

```
public class CustomizedTransferDamageEmailAlert extends
TransferDamageEmailAlertCommand {
    private Transfer transfer;
    public void setTransfer(Transfer transfer) {
        this.setTransfer(transfer);
    }
}
```

```
        this.transfer = transfer;
    }
    public String createSubjectLine(Locale locale) {
        return TranslatorServerCache.getMessage(locale, "Custom Transfer Damaged
Subject Line");
    }
    public String createEmailContent(Locale locale) {
        StringWriter emailContent = new StringWriter();
        PrintWriter printWriter = new PrintWriter(emailContent);
        printWriter.println(TranslatorServerCache.getMessage(locale,
            "Damaged goods received for transfer: ", transfer.getId()));
        printWriter.println();
        return emailContent.getBuffer().toString();
    }
}
```

The second step is very similar to other customization patterns: the factory implementation is altered to return the customized e-mail alert, and then `server.cfg` is updated to point at the new implementation. The custom factory implementation should extend the regular factory implementation and then override only the single `create()` method that it needs to:

```
public class CustomizedCommandFactoryImpl extends CommandFactoryImpl {
    public TransferDamageEmailAlertCommand createTransferDamageEmailAlertCommand()
    {
        return new CustomizedTransferDamageEmailAlert();
    }
}
```

To configure the factory, simply modify `server.cfg` and set the value to the customized class:

```
COMMAND_FACTORY_IMPL=customized.source.CustomizedCommandFactoryImpl
```

SIM Standalone Integration

For more information about RIB-based integrations, see "RIB-based Integration" in the *Oracle Retail Store Inventory Management Implementation Guide, Volume 2 – Integration with Oracle Retail Applications*.

Customizations

Integration with external systems has been decoupled from SIM. This integration code now resides in a `sim-int-<*>` project, where, `<*>` refers to the external system. Currently, only `sim-int-rib13` is fully implemented.

A `PollingCoordinatorBean` thread runs every five seconds, searching for polling timers that need to fire. When found, a `PollingTimerBean` thread is spawned with a List of `StagedMessage` objects. These `PollingTimerBean` threads process staged messages generically by calling the `PollingTimerCommand.processStagedMessages(List<StagedMessage>)`. Once inside the `PollingTimerCommand` method, a `SimMessageHandler` is looked up and a `handleMessages(List<StagedMessages>)` is called.

Each polling timer found in the `POLLING_TIMER` table corresponds to a `SimMessageHandler` defined by either the polling timer's message family or the message direction, or both. This mapping is done in the class that implements the `SimMessageHandlerFactoryInterface` defined in the `sim.cfg` in the key `MESSAGE_HANDLER_FACTORY_IMPL`.

The `PollingTimerCommand` is called by each `PollingTimerBean` to process message. To process the message, the `SimMessageHandlerFactory` is called to get the `SimMessageHandler` to use.

After messages are in the `STAGED_MESSAGE_TABLE`, polling timers act on these messages. `POLLING_TIMERS` are defined in the `POLLING_TIMER` table.

Creating a Custom Consumer

Do the following to create a custom consumer class:

1. Extend `SimMessageConsumer`.
2. Implement the `consume(List<DataExchangeObject> deos)` method.
3. Update `SimMessageConsumerFactoryImpl` to map the desired `SimMessageType` to your consumer.

Note: The message family to which the message type belongs will define which polling timer controls how many messages are processed, and how often those messages are processed.

Creating a Custom Stager

Do the following to create a custom stager:

1. Create a custom stager class by extending `SimMessageStager`.
2. Implement the `SimMessageType getMessageType()` method.
3. Implement the `List<DataExchangeObject> getDataExchangeObjects()` method.
4. Implement the `String getStoreID()` method.
5. Update `SimMessageStagerFactoryImpl` to return your custom `Stager` in the method for the desired business object.

Note: The message family to which the message type belongs will define which polling timer controls how many messages are processed, and how often those messages are processed.

Customizing Internationalization

Internationalization is the process of creating software that can be translated easily. Changes to the code are not specific to any particular market. SIM has been internationalized to support multiple languages.

This section describes customization settings and features of the software that enables the base application to be customized.

The PC client provides administrative screens for adding and altering translations.

Customizing a Language

The administrative section of the PC user interface has the ability to customize the translations of any language provided in the release of SIM. Users can create new keys that did not already exist in SIM. An understanding of English is necessary to use this feature of SIM. See the *Oracle Retail Store Inventory Management Users Guide* for more information about how to use these administrative features.

Do the following to add a new language to SIM:

1. [Insert a Record into RK_TRANSLATION_LOCALE.](#)
2. [Create an RK_TRANSLATION_DETAIL Row.](#)
3. [Create a Translation.](#)
4. [Assign a Correct Locale to a User.](#)

Insert a Record into RK_TRANSLATION_LOCALE

As an example, if Scottish Gaelic is to be added as a new language, insert the record listed in [Table 3-1](#) into the database. The LANGUAGE is the two character ISO 639 code for the language. The COUNTRY is the ISO 3166 two-character country code. VARIANT is not required:

Table 3-1 *RK_TRANSLATION_LOCALE Record*

Column	Value
LOCALE_ID	Insert a new unique ID here.
LANGUAGE	GD
COUNTRY	GB
VARIANT	Null
DESCRIPTION	Scottish Gaelic

Table 3–1 (Cont.) RK_TRANSLATION_LOCALE Record

Column	Value
UPDATE_DATE_TIME	The timestamp at the time of insert.

Create an RK_TRANSLATION_DETAIL Row

The second step is to create a row in the RK_TRANSLATION_DETAIL for every key in the RK_TRANSLATION_LEY table. The following SQL inserts a null value as the translation for each key (assumes the new locale ID in previous step was 99):

```
insert into rk_translation_detail
      (detail_id, locale_id, key_id, detail_value, update_date_time)
select to_char(rk_translation_detail_seq.nextval),
      99,
      key.key_id,
      null detail_value,
      trunc(date_utils.get_current_gmt())
from rk_translation_key key;
```

Create a Translation

Create a translation for each of the records inserted into RK_TRANSLATION_DETAIL. The SIM PC client contains administrative screens to perform this step. See the *Oracle Retail Store Inventory Management Users Guide*.

Assign a Correct Locale to a User

Update user information so that AC_USER.LANGUAGE and AC_USER.COUNTRY contain the same two character codes (GD & GB) as the new locale that was inserted.

Appendix: Web Services

Some SIM customers want to build their own handheld solution. Some reasons for this might include:

- Wireless technical limitation
- Special business process requirements
- Newer more efficient technologies

To support these new custom handheld deployments, SIM must expose new Web services that can be used by any external system. A generic approach like this enables SIM to be more modular and allow retailers to more easily integrate with certain SIM transactions.

Oracle Retail Store Inventory Management provides a number of Web services that expose various parts of the Store Inventory Management server's functionality. These Web services generally serve two purposes:

- Enable integration with external back-end systems
- Provide functionality to external client programs


Some of the Store Inventory Management Web services are intended for the backend of third-party systems, such as point-of-sale systems, to interact with Store Inventory Management. Examples of Web services that serve this purpose are Process UINs and Process Multiple Customer Orders.

Other Web services in Store Inventory Management are intended to be used by mobile client applications built by Store Inventory Management customers or other third parties. Examples of these are Store to Store Transfer and Return to Warehouse.

The Web services are not strictly segregated. There are some Web services that serve both purposes (for example, Item Lookup), and all Web services should be considered usable by any external system, whether or not it is a client program.

Store Inventory Management Web services are not all read-only Web services. Store Inventory Management provides some Web services that look up existing Store Inventory Management data and some that manipulate that data or add new data.

[Figure A-1](#) demonstrates a Web service process flow:

Figure A-1 Web Service Process Flow

Asynchronous Operations

Most Web services in Store Inventory Management work synchronously; the Web services accept input, validate and process the input, then return results. However, some Web services in Store Inventory Management work on bulk data and work asynchronously (for example, Process Multiple Customer Orders and Process Multiple POS Transactions). These Web services accept input of many data items at once, but do not process them all immediately. Instead the Web services perform minor validation on the data, store the data, then return to the caller. After the Web service returns to the caller, Store Inventory Management's asynchronous processing framework initiates the remainder of the processing. The Web services that follow this pattern mention refer to this functionality in their service descriptions in the WSDL.

Application Programming Interface (API)

Store Inventory Management's Web services are SOAP-based Web services. All services are defined in one WSDL 1.1 file (sim-ws.wsdl), and the various data types used in the Web services are defined in XSD files. The XSD files are split by functional area into the following files:

- SIMBaseType.xsd
- ItemLookup.xsd
- InventoryLookup.xsd
- UINSerialization.xsd
- CustomerOrder.xsd
- ItemBasket.xsd
- PosTransaction.xsd
- SaleReturnTxn.xsd
- InventoryAdjustment.xsd
- Transfer.xsd

- StockReturn.xsd

Implementation

Web service implementation on the Store Inventory Management server is done in a top-down fashion, meaning that a Web service's API is first defined in WSDL and XSD, and then supporting Java classes are generated from the WSDL using Oracle tools. These classes are then used to connect the Web services to existing Store Inventory Management server functionality.

Security

Store Inventory Management Web services are installed out-of-the-box with basic HTTP authentication enabled. If a different scheme is required, the services can be secured at a client site with any SOAP-friendly Web service authentication mechanism, for example, WS-Security.

Deployment

The Store Inventory Management server application is deployed as a Java EE application (sim.ear). The Store Inventory Management Web service WSDL, XSD, generated Java classes, and implementation Java classes are all deployed as a Web module (sim-ws.war) inside the server application. To access the WSDL in a running Store Inventory Management instance, go to the following URL:

<http://<orsim-server-url>:<orsim-server-port>/sim-ws/simWebService?WSDL>

Definition Files and Services

Table A-1 identifies the current WSDL and XSD definition files in Store Inventory Management:

Table A-1 Web Service Definition Files

Name	Description
sim-ws.wsdl	Contains the definition of all Web services in SIM.
SIMBaseType.xsd	Contains message elements definitions common to all Web services.
CustomerOrder.xsd	Contains the message element definitions for customer order Web services.
InventoryAdjustment.xsd	Contains the message element definitions for inventory adjustment Web services.
InventoryLookup.xsd	Contains the message element definitions for item inventory lookup Web services.
ItemBasket.xsd	Contains the message element definitions for item basket Web services.
ItemLookup.xsd	Contains the message element definitions for item lookup Web services.
PosTransaction.xsd	Contains the message element definitions for POS transaction Web services.

Table A-1 (Cont.) Web Service Definition Files

Name	Description
SaleReturnTxn.xsd	Contains the message element definitions for sale return transaction Web services.
StockReturn.xsd	Contains the message element definitions for stock return Web services.
Transfer.xsd	Contains the message element definitions for stock transfer Web services.
UINSerialization.xsd	Contains the message element definitions for serial number based Web services.

Table A-2 is a list of all Web services in Store Inventory Management:

Table A-2 Web Services

Name	XSD File	Description
lookupItem	ItemLookup	Lookup basic item header information for given search criteria.
lookupItemDetail	ItemLookup	Lookup extensive item information for given item ID.
lookupItemMarkdowns	ItemLookup	Lookup item markdown information for given search criteria.
lookupInventory	InventoryLookup	Lookup item inventory information for given search criteria.
lookupUINDetail	UINSerialization	Lookup item or UIN information based on several different inconsistent inputs.
lookupUIN	UINSerialization	Look basic UIN information for a UIN.
createUIN	UINSerialization	Create a new UIN in the system.
processUINs	UINSerialization	Process UINs and performs updates with input information.
updateUIN	UINSerialization	Processes a single UIN and updates its information in SIM.
processCustomerOrder	CustomerOrder	Process a customer order and updates its information in SIM.
processMultipleCustomerOrders	CustomerOrder	Processes many customer orders and updates their information in SIM.
lookupItemBasket	ItemBasket	Lookup the detailed information of an item basket.
processMultiplePosTxns	PosTransaction	Process POS transactions and update the information in SIM.
updateSaleReturn	SaleReturnTxn	Process sale return transaction and update its information in SIM.
processInventoryAdjustments	InventoryAdjustment	Process inventory adjustments and update the information in SIM.

Table A–2 (Cont.) Web Services

Name	XSD File	Description
lookupTransferHeader	Transfer	Lookup basic transfer header information for given search criteria.
lookupTransferDetail	Transfer	Retrieve detailed transfer information for the given transfer ID.
updateTransfer	Transfer	Process the transfer and update its information in SIM.
lookupReturnHeader	StockReturn	Lookup basic return header information for given search criteria.
lookupReturnDetail	StockReturn	Retrieve detailed return information for the given return ID.
updateReturn	StockReturn	Process the return and update its information in SIM.

Web Service APIs

The following describes the Web service APIs for SIM.

lookupItem

The following describes the lookupItem Web service API.

Table A–3 lookupItem

Input Message	Output Message	Fault
lookupItemRequest	lookupItemResponse	lookupItemFault

Table A–4 LookupItemRequest

Name	Type	Required
StoreId	String	No
UsedId	String	No
ItemIdOrBarcode	String	No
UIN	String	No
ItemShortDescription	String	No
ItemLongDescription	String	No
SupplierId	String	No
SupplierName	String	No
PrimarySupplier	Boolean	Yes
DepartmentId	String	No
ClassId	String	No
SubclassId	String	No
IncludeNonRanged	Boolean	Yes
SearchLimit	Integer	Yes

Table A-5 LookupItemResponse

Name	Type	Required
Items	LookupItemResponseInfo	0 --> Unbounded

Table A-6 Response Info

Name	Type	Required
ItemId	String	Yes
ItemType	ItemTypeWSType	Yes
ShortDescription	String	Yes
LongDescription	String	No
DepartmentName	String	No
ClassName	String	No
SubclassName	String	No
SupplierId	String	No
SupplierName	String	No
IsRanged	Boolean	Yes

Table A-7 ItemTypeWSType

Name
ITEM
CONSIGNMENT
CONCESSION
NON_INVENTORY
PACK_SIMPLE
PACK_COMPLEX
PACK_BREAKABLE

Table A-8 LookupItemFault

Name	Type	Required
errorMessages	ErrorMessageWSType	0 --> Unbounded
storied	String	No

Table A-9 ErrorMessageWSType

Code	Description
INVALID_STORE	If Store ID is left empty or the store cannot be found for the ID.

lookupItemDetail

The following describes the lookupItemDetail Web service API.

Table A-10 *lookupItemDetail*

Input Message	Output Message	Fault
lookupItemDetailRequest	lookupItemDetailResponse	lookupItemFault

Table A-11 *LookupItemDetailRequest*

Name	Type	Required
StoreId	String	No
UserId	String	No
ItemId	String	Yes

Table A-12 *LookupItemDetailResponse*

Name	Type	Required
ItemId	String	Yes
StoreId	String	No
ParentId	String	No
ItemType	ItemTypeWSType	Yes
IsSellable	Boolean	Yes
IsOrderable	Boolean	Yes
ShortDescription	String	Yes
LongDescription	String	No
DepartmentId	String	Yes
DepartmentName	String	No
ClassId	String	No
ClassName	String	No
SubclassId	String	No
SubclassName	String	No
UnitOfMeasure	String	Yes
Status	ItemStatusWSType	Yes
DefaultCaseSize	Decimal	Yes
UINType	UINWSType	No
UINLabel	String	No
UnavailableQty	Decimal	Yes
CustomerReservedQty	Decimal	Yes
InTransitQty	Decimal	Yes
StockInDeliveryBay	Decimal	Yes
StockInBackRoom	Decimal	Yes
StockOnShopFloor	Decimal	Yes

Table A-12 (Cont.) LookupItemDetailResponse

Name	Type	Required
StockOnHand	Decimal	Yes
AvailableInventory	Decimal	Yes
TransferReservedQty	Decimal	Yes
VendorReturnQty	Decimal	Yes
OrderedQty	Decimal	Yes
ReceivedTodayQty	Decimal	Yes
LastReceivedDate	Date	No
PrimarySupplierId	String	No
PrimarySupplierName	String	No
PrimarySequenceId	String	No
PrimarySequenceName	String	No
UPC	String	No
VPN	String	No
SuggestedTicketType	String	No
IsStoreOrderAllowed	Boolean	Yes
IsStoreOrderReplenishmentAllowed	Boolean	Yes
IsMultipleDeliveryAllowed	Boolean	Yes
IsSOHInquiryAtPackLevel	Boolean	Yes
DiffType1	String	No
DiffDescription1	String	No
DiffType2	String	No
DiffDescription2	String	No
DiffType3	String	No
DiffDescription3	String	No
DiffType4	String	No
DiffDescription4	String	No
PriceType	PriceWSType	No
PromotionType	PromotionWSType	No
RetailPrice	Decimal	No
RetailCurrency	String	No
RetailEffectiveDate	Date	No
SellingUnitOfMeasure	String	No
ReplenishmentMethod	String	No
MultiUnitQuantity	Decimal	No
MultiUnitPrice	Decimal	No
MultiUnitCurrency	String	No
MultiUnitSellingUOM	String	No

Table A-12 (Cont.) LookupItemDetailResponse

Name	Type	Required
NextDeliveryDate	Date	No
ItemDetailSuppliers	LookupItemDetailSupplier	0 --> Unbounded
ItemDetailImages	LookupItemDetailImage	0 --> Unbounded

Table A-13 LookupItemDetailSupplier

Name	Type	Required
SupplierId	String	Yes
SupplierName	String	Yes

Table A-14 LookupItemDetailImage

Name	Type	Required
URL	String	Yes

Table A-15 ItemStatusWSType

Name
NONE
ACTIVE
INACTIVE
DISCONTINUED
DELETED
AUTO_STOCKABLE
NON_RANGED

Table A-16 UINWSType

Name
SERIAL_NUMBER
AGSN

Table A-17 PriceWSType

Name
CLEARANCE
PROMOTIONAL
PERMANENT

Table A-18 PromotionWSType

Name
COMPLEX
SIMPLE

Table A-18 (Cont.) PromotionWSType

Name
THRESHHOLD
CREDIT

Table A-19 LookupItemFault

Name	Type	Required
errorMessages	ErrorMessageWSType	0 --> Unbounded
storied	String	No

Table A-20 ErrorMessageWSType

Code	Description
INVALID_STORE	If Store ID is left empty or the store cannot be found for the ID.
INVALID_ITEM	If Item ID is left empty or the item cannot be found for the ID.

lookupItemMarkdowns

The following describes the lookupItemMarkdowns Web service API.

Table A-21 lookupItemMarkdowns

Input Message	Output Message	Fault
lookupItemMarkdownsRequest	lookupItemMarkdownsResponse	lookupItemFault

Table A-22 LookupItemMarkdownRequest

Name	Type	Required
StoreId	String	Yes
UserId	String	No
MarkdownDate	DateTime	Yes
PriceType	PriceWSType	No
PromotionId	String	No
DepartmentId	String	No
ClassId	String	No
SubclassId	String	No
ItemId	String	No
SequenceId	String	No

Table A-23 LookupItemMarkdownResponse

Name	Type	Required
ItemMarkdowns	LookupItemMarkdownResponseInfo	0 --> Unbounded

Table A–24 *LookupItemMarkdownResponseInfo*

Name	Type	Required
ItemId	String	Yes
ItemType	ItemTypeWSType	Yes
ShortDescription	String	Yes
LongDescription	String	No
DepartmentId	String	Yes
DepartmentName	String	Yes
ClassId	String	No
ClassName	String	No
SubclassId	String	No
SubclassName	String	No
PriceType	PriceTypeWSType	Yes
Currency	String	Yes
CurrentPrice	Decimal	Yes
CurrentSellingUOM	String	Yes
NewPrice	Decimal	Yes
NewSellingUOM	String	Yes
CurrentMultiUnits	Decimal	No
CurrentMultiUnitPrice	Decimal	No
CurrentMultiUnitSellingUOM	String	No
NewMultiUnits	Decimal	No
NewMultiUnitPrice	Decimal	No
NewMultiUnitSellingUOM	String	No

Table A–25 *LookupItemFault*

Name	Type	Required
errorMessages	ErrorMessageWSType	0 --> Unbounded
storeId	String	No

Table A–26 *ErrorMessageWSType*

Code	Description
INVALID_STORE	If Store ID is left empty, is not numeric, or the store cannot be found for the ID.
INVALID_DEPARTMENT_ID	If Department ID is not numeric.
INVALID_CLASS_ID	If Class ID is not numeric.
INVALID_SUBCLASS_ID	If Subclass ID is not numeric.
INVALID_PROMOTION_ID	If Promotion ID is not numeric.
INVALID_SEQUENCE_ID	If Sequence ID Is not numeric.

Table A–26 (Cont.) ErrorMessageWSType

Code	Description
INVALID_MARKDOWN_DATE	If Markdown Date is left empty.

lookupReturnHeader

The following describes the lookupReturnHeader Web service API.

Table A–27 lookupReturnHeader

Input Message	Output Message	Fault
lookupReturnHeaderRequest	lookupReturnHeaderResponse	returnFault

Table A–28 LookupReturnHeaderRequest

Name	Type	Required
StoreId	String	Yes
UserId	String	No
ReturnId	String	No
ExternalId	String	No
ContextTypeCode	String	No
ShipToEntityType	ShipToEntityType	No
ShipToEntityId	String	No
FromDate	Date	No
ToDate	Date	No
ReasonCode	String	No
Status	ReturnStatusWSType	No

Table A–29 LookupReturnHeaderResponse

Name	Type	Required
LookupReturnHeaderResponse	LookupReturnHeaderResponseDetail	0 --> Unbounded Details

Table A–30 LookupReturnHeaderResponseDetail

Name	Type	Required
ReturnId	String	Yes
ExternalId	String	No
StoreId	String	Yes
AuthorizationCode	String	No
ContextType	String	No
ContextValue	String	No
ShipToEntityType	ShipToEntityTypeWSType	Yes
ShipToEntityId	String	Yes

Table A-30 (Cont.) LookupReturnHeaderResponseDetail

Name	Type	Required
ShipToEntityName	String	Yes
NotAfterDate	DateTime	No
Status	ReturnStatusWSType	Yes
StatusDate	DateTime	Yes
NumberOfLineItems	Decimal	Yes

Table A-31 ShipToEntityWSType

Name
SUPPLIER
WAREHOUSE
FINISHER

Table A-32 ReturnStatusWSType

Name
PENDING
REQUESTED
DISPATCHED
RECEIVED
ACTIVE
CANCELED

Table A-33 ReturnFault

Name	Type	Required
errorMessages	ErrorMessageWSType	0 --> Unbounded
itemProblems	ItemProblemWSInfo	0 --> Unbounded

Table A-34 ItemProblemWSInfo

Name	Type	Required
itemId	String	No
errorMessage	ItemErrorMessageWSType	Yes

Table A-35 ErrorMessageWSType

Code	Description
INVALID_STORE	If Store ID is left empty, is not numeric, or the store cannot be found for the ID.
INVALID_RETURN_ID	If the ID of the return is entered but is not numeric.

Table A-35 (Cont.) ErrorMessageWSType

Code	Description
INVALID_CONTEXT_TYPE_CODE	If a context type does not exist for this code.

lookupReturnDetail

The following describes the lookupReturnDetail Web service API.

Table A-36 lookupReturnDetail

Input Message	Output Message	Fault
lookupReturnDetailRequest	lookupReturnDetailResponse	returnFault

Table A-37 LookupReturnDetailRequest

Name	Type	Required
StoreId	String	Yes
UserId	String	No
ReturnId	String	Yes

Table A-38 LookupReturnDetailResponse

Name	Type	Required
ReturnId	String	Yes
ExternalId	String	No
StoreId	String	Yes
AuthorizationCode	String	No
ContextType	String	No
ContextValue	String	No
ShipToEntityType	ShipToEntityWSType	Yes
ShipToEntityId	String	Yes
ShipToEntityName	String	Yes
NotAfterDate	DateTime	No
Status	ReturnStatusWSType	Yes
StatusDate	DateTime	Yes
TransactionCode	String	Yes
Comments	String	No
CreateUser	String	Yes
CreateDate	DateTime	Yes
DispatchDate	DateTime	No
CompleteDate	DateTime	No
NumberOfLineItems	Decimal	Yes
LookupReturnItemDetails	LookupReturnItemDetail	0 --> Unbounded

Table A–39 *LookupReturnItemDetail*

Name	Type	Required
Id	String	Yes
ItemId	String	Yes
ItemType	ItemTypeWSType	Yes
ShortDescription	String	Yes
LongDescription	String	Yes
DepartmentId	String	Yes
DepartmentName	String	Yes
ClassId	String	No
ClassName	String	No
SubclassId	String	No
SubclassName	String	No
UnitOfMeasure	String	Yes
CaseSize	Decimal	Yes
Comment	String	No
Quantity	Decimal	No
QuantityRequested	Decimal	No
ReasonCode	String	Yes
ReasonDescription	String	Yes

Table A–40 *ReturnFault*

Name	Type	Required
errorMessages	ErrorMessageWSType	0 --> Unbounded
itemProblems	ItemProblemWSInfo	0 --> Unbounded

Table A–41 *ErrorMessageWSType*

Code	Description
INVALID_STORE	If Store ID is left empty, is not numeric, or the store cannot be found for the ID.
INVALID_RETURN_ID	If the ID of the return is left blank, is not numeric, or the return does not exist.

updateReturn

The following describes the updateReturn Web service API.

Table A-42 *updateReturn*

Input Message	Output Message	Fault
updateReturnRequest	updateReturnResponse	returnFault

Table A-43 *UpdateReturnRequest*

Name	Type	Required
ReturnId	String	Yes
StoreId	String	Yes
UserId	String	No
Action	ReturnActionWSType	Yes
AuthorizationCode	String	No
Comments	String	No
Items	UpdateReturnItemRequest	0 --> Unbounded

Table A-44 *UpdateReturnItemRequest*

Name	Type	Required
ItemId	String	Yes
ReasonCode	String	Yes
Quantity	Decimal	Yes
Action	ReturnItemActionWSType	Yes

Table A-45 *UpdateReturnResponse*

Name	Type	Required
ReturnId	String	Yes

Table A-46 *ReturnActionWSType*

Name
CANCEL
UPDATE
UPDATE_AND_DISPATCH

Table A-47 *ReturnItemActionWSType*

Name
UPDATE
DELETE

Table A-48 ReturnFault

Name	Type	Required
errorMessages	ErrorMessageWSType	0 --> Unbounded
itemProblems	ItemProblemWSInfo	0 --> Unbounded

Table A-49 ItemProblemWSInfo

Name	Type	Required
itemId	String	No
errorMessage	ItemErrorMessageWSType	Yes

Table A-50 ErrorMessageWSType

Code	Description
INVALID_STORE	If Store ID is left empty, is not numeric, or the store cannot be found for the ID.
INVALID_RETURN_ID	If the ID of the return is left blank, is not numeric, or the return does not exist.
UNABLE_TO_LOCK_RETURN_FOR_UPDATE	If the Return is currently being modified by another user.
USER_ID_MISSING	If no user ID is provided.

Table A-51 ItemErrorMessageWSType

Code	Description
LINE_ITEM_NOT_FOUND	No current line item exists on the Return for the item ID in the message.
INVALID_RETURN_REASON	No return reason exists for the given line item reason code in the message.
INVALID_RETURN_QUANTITY	If quantity is left blank or is negative.

lookupTransferHeader

The following describes the lookupTransferHeader Web service API.

Table A-52 lookupTransferHeader

Input Message	Output Message	Fault
lookupTransferHeaderRequest	lookupTransferHeaderResponse	transferFault

Table A-53 LookupTransferHeaderRequest

Name	Type	Required
storeId	String	Yes
OtherStoreId	String	No
userId	String	No
Status	TransferQueryStatusWSType	No

Table A-53 (Cont.) LookupTransferHeaderRequest

Name	Type	Required
TransferId	String	No
ExternalId	String	No
ItemId	String	No
FromDate	Date	No
ToDate	Date	No
ContextTypeCode	String	No

Table A-54 LookupTransferHeaderResponse

Name	Type	Required
LookupTransferHeaderResponse Details	LookupTransferHeaderResponse Detail	0 --> Unbounded

Table A-55 LookupTransferHeaderResponseDetail

Name	Type	Required
TransferId	String	Yes
ExternalId	String	No
SendingStoreId	String	Yes
SendingStoreName	String	No
ReceivingStoreId	String	Yes
ReceivingStoreName	String	No
Status	TransferStatusWSType	Yes
StatusDate	Calendar	No
CreateUser	String	Yes
ApprovalUser	String	No
ReceiveUser	String	No
NumberOfLineItems	Decimal	Yes

Table A-56 TransferQueryStatusWSType

Name
ACTIVE
ACTIVE_INBOUND
ACTIVE_OUTBOUND
NEW
PENDING_REQUEST
AWAITING_RESPONSE
OUTBOUND_REJECTED
INBOUND_REJECTED
IN_PROGRESS

Table A-56 (Cont.) TransferQueryStatusWSType

Name
INBOUND_PICKING
IN_TRANSIT
DISPATCHED
RECEIVING
CLOSED
RECEIVED
CANCELLED_INBOUND
CANCELLED_REQUEST
CANCELLED_TRANSFER

Table A-57 TransferStatusWSType

Name
NEW
PENDING
REJECTED
CANCELLED_REQUEST
IN_PROGRESS
DISPATCHED
RECEIVING
RECEIVED
CANCELLED_TRANSFER

Table A-58 TransferFault

Name	Type	Required
errorMessages	ErrorMessageWSType	0 --> Unbounded
itemProblems	ItemProblemWSInfo	0 --> Unbounded

Table A-59 ItemProblemWSInfo

Name	Type	Required
itemId	String	No
errorMessage	ItemErrorMessageWSType	Yes

Table A-60 ErrorMessageWSType

Code	Description
INVALID_STORE	If Store ID is left empty, is not numeric, or the store cannot be found for the ID.
INVALID_OTHER_STORE	If the ID of the other store involved with the transfer is left blank, is not numeric, or does not exist.

Table A–60 (Cont.) ErrorMessageWSType

Code	Description
INVALID_QUERY_STATUS	If the transfer status to query for is entered, but does not match a valid transfer status.
INVALID_EXTERNAL_ID	If the External ID is not numeric.
INVALID_CONTEXT_TYPE_CODE	If a context type does not exist for this code.

lookupTransferDetail

The following describes the lookupTransferDetail Web service API.

Table A–61 lookupTransferDetail

Input Message	Output Message	Fault
lookupTransferDetailRequest	lookupTransferDetailResponse	transferFault

Table A–62 LookupTransferDetailRequest

Name	Type	Required
StoreId	String	Yes
UserId	String	No
TransferId	String	Yes

Table A–63 LookupTransferDetailResponse

Name	Type	Required
TransferId	String	Yes
CreateStoreId	String	Yes
SendingStoreId	String	Yes
SendingStoreName	String	No
ReceivingStoreId	String	Yes
ReceivingStoreName	String	No
ExternalId	String	No
Status	TransferStatusWSType	Yes
CreateUser	String	Yes
UpdateUser	String	No
ApprovalUser	String	No
ShippedUser	String	No
ReceiveUser	String	No
CreateDate	Date	Yes
UpdateDate	Date	No
ApprovalDate	Date	No
ShipDate	Date	No

Table A-63 (Cont.) LookupTransferDetailResponse

Name	Type	Required
ReceiveDate	Date	No
TransferComments	String	No
RequestComments	String	No
DeliverySlotId	String	No
ContextType	String	No
ContextValue	String	No
LookupTransferItemDetails	LookupTransferItemDetail	0 --> Unbounded

Table A-64 LookupTransferItemDetail

Name	Type	Required
Id	String	Yes
ItemId	String	Yes
ItemType	ItemTypeWSType	Yes
ShortDescription	String	Yes
LongDescription	String	Yes
DepartmentId	String	Yes
DepartmentName	String	Yes
ClassId	String	No
ClassName	String	No
SubclassId	String	No
SubclassName	String	No
UnitOfMeasure	String	Yes
CaseSize	Decimal	Yes
RequestedQuantity	Decimal	No
ApprovedQuantity	Decimal	No
TransferQuantity	Decimal	No
DamagedQuantity	Decimal	No
ReceivedQuantity	Decimal	No

Table A-65 TransferFault

Name	Type	Required
errorMessages	ErrorMessageWSType	0 --> Unbounded
itemProblems	ItemProblemWSInfo	0 --> Unbounded

Table A-66 ErrorMessageWSType

Code	Description
INVALID_STORE	If Store ID is left empty, is not numeric, or the store cannot be found for the ID.

Table A-66 (Cont.) ErrorMessageWSType

Code	Description
INVALID_TRANSFER_ID	If Transfer ID is left empty, is not numeric, or a transfer cannot be found for the ID.

updateTransfer

The following describes the updateTransfer Web service API.

Table A-67 updateTransfer

Input Message	Output Message	Fault
updateTransferRequest	updateTransferResponse	transferFault

Table A-68 UpdateTransferRequest

Name	Type	Required
TransferId	String	No
UserId	String	No
StoreId	String	Yes
ReceivingStoreId	String	Yes
Comments	String	No
Action	TransferActionWSType	Yes
Items	UpdateTransferItemRequest	0 --> Unbounded

Table A-69 UpdateTransferItemRequest

Name	Type	Required
ItemId	String	Yes
Action	TransferItemActionWSType	Yes
TransferQuantity	Decimal	Yes

Table A-70 UpdateTransferResponse

Name	Type	Required
TransferId	String	Yes

Table A-71 TransferActionWSType

Name
CREATE
CREATE_AND_DISPATCH
UPDATE
UPDATE_AND_DISPATCH

Table A-72 *TransferItemActionWSType*

Name
ADD
EDIT

Table A-73 *TransferFault*

Name	Type	Required
errorMessages	ErrorMessageWSType	0 --> Unbounded
itemProblems	ItemProblemWSInfo	0 --> Unbounded

Table A-74 *ItemProblemWSInfo*

Name	Type	Required
itemId	String	No
errorMessage	ItemErrorMessageWSType	Yes

Table A-75 *ErrorMessageWSType*

Code	Description
INVALID_STORE	If Store ID is left empty, is not numeric, or the store cannot be found for the ID.
INVALID_OTHER_STORE	If the ID of the other store involved with the transfer is left blank, is not numeric, or does not exist.
INVALID_TRANSFER_ID	If transfer ID is not a number or no transfer is found.
INVALID_STATUS	If transfer is not in a valid status for update (IN_PROGRESS).
TRANSFER_ID_NOT_NULL_ON_CREATE	If the action is CREATE or CREATE_AND_DISPATCH, and the transfer ID has been included.
TRANSFER_ID_NOT_PROVIDED	If the action is UPDATE or UPDATE_AND_DISPATCH, and the transfer ID has not been included.
USER_NOT_PROVIDED	If UpdateUser is not included in message.

Table A-76 *ItemErrorMessageWSType*

Code	Description
INVALID_ITEM_ACTION_FOR_TRANSFER_CREATE	If request contained an action for an item other than ADD.
INVALID_ITEM_ID	No item was found for item identifier.
TRANSFER_ITEM_ALREADY_EXISTS	Item to add to transfer already exists on transfer.
ITEM_ID_MISSING	If item ID was not included in item level message.
ITEM_NOT_RANGED	If item ID is not ranged at sending store or receiving store.

Table A-76 (Cont.) ItemErrorMessageWSType

Code	Description
TRANSFER_ITEM_NOT_FOUND	Item to update does not exist on the transfer.
TRANSFER_QUANTITY_MISSING	If transfer quantity was not included in item level message.
TRANSFER_QUANTITY_NEGATIVE	If transfer quantity was a negative number.

processItemImage

The following describes the processItemImage Web service API.

Table A-77 processItemImage

Input Message	Output Message	Fault
processItemImageRequest	processItemImageResponse	

Table A-78 processLinesItemImageRequest

Name	Type	Required
StoreId	String	Yes
ItemId	String	Yes
ImageUrl	String	Yes
ImageType	ImageWSType	Yes
ImageName	String	Yes
StartDate	Calendar	No
EndDate	Calendar	No

Table A-79 processItemImageResponse

Name	Type	Required
Status	String	Yes

Table A-80 ImageWSType

Name
ITEM_IMAGE
QR_IMAGE

Table A-81 ErrorMessageWSType

Code	Description
INVALID_STORE_ID	If Store ID is left empty, is not numeric, or the store cannot be found for the ID.
INVALID_ITEM_ID	If the item ID is left blank, is not numeric, or the item does not exist.

Web Services

The following describes the Web services for SIM.

Lookup Return Detail

This Web service returns to the calling Web service detailed return information.

SIM Inbound Information

Store ID and Return ID

SIM Outbound Information

Multiple item IDs can be returned with the return header information

Fail Messages

- Return number invalid
- Location invalid
- Fail messages:

This Web service must be able to support the following generic process:

1. User selects a specific return.
2. SIM provides all the return header and item information.
3. The external UI displays this information to the user.

Web Service Input

Calling attribute:

- Location ID (required)
- Return ID (required)

Web Service Output

- Return ID
- External return ID
- Store ID
- Return Authorization ID
- Context type
- Context value
- Ship to entity type:
 - Supplier
 - Warehouse
 - Finisher
- Ship to entity ID
- Ship to entity description
- Not after date

- Status
- Last status date change
- Transaction Code
- Comments
- Create user
- Create Date
- Dispatch Date
- Complete Date
- Number of line items
- Item details (can be multiple):
 - Item ID
 - Item Type
 - Short description
 - Long Description
 - Department ID
 - Department Description
 - Class ID
 - Class description
 - Subclass ID
 - Subclass description
 - UOM
 - Case Size
 - Comment
 - Quantity
 - Quantity requested
 - Reason Code:
 - * RK_CODE_DETAIL.CODE_ID type, RTVR, ID O
 - Reason description, for example, overstock.

Web Service Error Messages

Table A-82 Lookup Return Detail Error Messages

ID	Event	Error Message Description	Result
1	Invalid return ID	If the return ID is left empty, or a non existing return ID is provided.	
2	Invalid Store ID	If Store ID is left empty or the store cannot be found for the ID	

Lookup Return Header

This Web service enables the user to find supplier or warehouse returns that need to be executed.

SIM Inbound Information

- Store ID
- Return ID
- Context Value
- Ship to entity type and ID
- External Return ID
- Reason
- Status
- From and to date

SIM Outbound Information

Multiple returns can be returned with the following info:

- Internal and External Return ID
- Store ID
- Authorization code
- Context type and value
- Ship to entity type
- Ship to
- Type and description
- Not after date
- Status
- Number of lines
- Status date

Fail Messages

- Invalid store ID
- Invalid return ID

This Web service must be able to support the following generic process:

1. User scans or enters one or more elements of the previous criteria to identify the return.
2. SIM will return generic returns information.
3. The external UI uses this information to allow the user to identify the specific return they want to work with.

Web Service Input

Calling attribute:

- Location ID (required)

- Return ID
- Context Type
- Ship to type:
 - Supplier
 - Warehouse
 - Finisher
- External return ID
- Reason:
 - Depends on values in RK_CODE_DETAIL.CODE_ID (RTVR)
- Status:
 - Active
 - Cancelled
 - Dispatched
 - Pending
 - Requested
- From date
- To date

Web Service Output

- Return ID
- External return ID
- Store ID
- Return Authorization value
- Context Type
- Context Value
- Ship to Entity Type
- Ship to Entity ID
- Ship to entity description
- Not after date:
 - Populated by use of MRTs in RMS
- Status
- Status Date
 - Last date Return changed status
- Number of line items

Web Service Error Messages

Table A-83 *Lookup Return Header Error Messages*

ID	Event	Error Message Description	Result
1	Invalid Store	If Store ID is left empty or the store cannot be found for the ID	

Item Lookup

When adding an item to a transfer or checking the price of an item, SIM also needs to be able to add a Web service that will return item information.

SIM Inbound Information

- Item ID or Barcode
- Location
- UIN
- Long or short description
- Supplier information
- Merchandise hierarchy
- Ranged or not

SIM Outbound Information

Multiple item IDs can be returned with the following info:

- Item ID
- Item type
- Short/long description
- Merchandise Hierarchy ID/description
- Supplier ID/name
- Ranged or not

Fail Messages

This Web service must be able to support the following generic process:

1. User scans or enters one or more elements of the above criteria
2. SIM will return generic item information
3. The external UI will use this information to call up more details (different WS) or use the info as is.

Web Service Input

Calling attribute:

- Location ID (required)
- Item ID or barcode
- UIN
- Short description

- Long description
- Supplier ID
- Supplier description
- Primary supplier indicator (required):
 - True
 - False
- Department
- Class
- Subclass
- Include non-ranged items (required):
 - True
 - False
- Search limit
 - Determines how many max records can be returned

Web Service Output

- Item ID
- Item Type
 - 0 regular item
 - 5 consignment
 - 10 concession
 - 12 Non-Inventory
 - 15 Simple Pack
 - 20 Complex Pack
 - 25 Simple Conversion
- Short description
- Long description (contains diffs)
- Department description
- Class description
- Subclass description
- Supplier ID
- Supplier Name
- Is item ranged or not

Web Service Error Messages

Table A-84 *Item Lookup Error Messages*

ID	Event	Error Message Description	Result
1	Required fields missing	Required primary supplier and ranged indicator are missing	
2	Invalid Store	If Store ID is left empty or the store cannot be found for the ID	

Item Detail Lookup

When adding an item to a transfer or checking the price of an item, SIM must also be able to add a Web service that will return item information.

A third party UI uses this Web service to get detailed item information. The system requires a valid item and a store ID.

The Web service allows the lookup of an item/loc record if the item location relationship does not exist and the **Allow non-range item** admin system option is set.

The Web service always returns all quantities at the SUOM level, regardless of any of the other system/store options.

In case of a notional pack, SIM calculates the estimated quantities if the Simple Pack Conversion is set up to allow the display of a calculated quantity (SOH inquiry).

SIM Inbound Information

Location and Item Number (both are required)

SIM Outbound Information

All item attribute information:

- Inventory buckets
- Item loc descriptions
- Supplier information (including primary)
- Merchandise hierarchy
- Size/color information
- Item Attributes (sellable and so forth)
- Current Pricing info
- Ordering Attributes
- URLs of item images

Fail Messages

- Item number invalid
- Location invalid
- No item found

This Web service must be able to support the following generic process:

1. User scans or enters an item.
2. SIM will return item information.

3. Item is added to the transaction or displayed on its own so the user can see different information about the item.

Web Service Input

Calling attribute:

- Store ID
- Item ID

Web Service Output

- Item ID
- Store ID
- Parent Item ID
- Item Type
- Sellable
- Orderable
- Short description
- Long Description
- Merchandise Hierarchy
 - Department ID
 - Department description
 - Class ID
 - Class description
 - Subclass ID
 - Subclass description
- UOM
- Item Status
- Default Case Size
- UIN Type
- UIN Label
- Inventory Information
 - Unavailable Quantity
 - Customer Reserved Quantity
 - In Transit Quantity
 - Delivery Bay Quantity
 - Back Room Quantity
 - Shop floor Quantity
 - SOH
 - Available Quantity
 - Transfer Reserved Quantity

- Ordered Quantity
 - Received Today Quantity
 - Received date
- Primary supplier
- Primary supplier description
- UPC
- VPN
- Suggested Ticket Type
- Store Order Allowed
- Store Order Replenishment Allowed
- Multiple Deliveries Allowed
- SOH Inquiry At Pack Level
- Diff Type 1
- Diff Type 1 Description
- Diff Type 2
- Diff Type 2 Description
- Diff Type 3
- Diff Type 3 Description
- Diff Type 4
- Diff Type 4 Description
- Price Information
 - Price Type
 - Promotion Type
 - Retail Price
 - Retail Currency
 - Retail price Effective date
 - Selling UOM
 - Multi Unit Price Quantity
 - Multi Unit Price
 - Multi Unit Currency
 - Multi Unit Selling UOM
- Replenishment Method
- Next Delivery Date
- Item Detail Supplier
- Item Detail Image (can be multiple)
- URL
- Item suppliers (can be multiple)

- Supplier ID
- Supplier Name

Web Service Error Messages

Table A-85 *Item Detail Lookup Error Messages*

ID	Event	Error Message Description	Result
1	User provides non existing Item ID or it is left empty	Invalid Item	
2	User provides non existing store ID or it is left empty	Invalid Store	

Update Return

This Web service enables the user to do the following:

- Make changes to item quantities on a SIM return.
- Cancel returns.

SIM Inbound Information

- User ID
- Return ID
- Store ID
- Authorization ID
- Comments and action
- Items which each have a quantity, reason code and an action and quantity against them.

SIM Outbound Information

- Transfer ID

Fail Messages

- Invalid store ID
- Invalid other store ID
- Invalid return ID
- Transfer ID not null on create
- Transfer ID is not provided
- User not provided

This Web service must be able to support the following generic process:

1. The user selects a transfer ID
2. SIM returns all transfer information
3. The external UI uses this information to enable the user to add or change items and quantities as well as dispatch or create new transfers.

Web Service Input

Calling attribute:

- Return ID (required)
- User ID
- Shipping Store ID (required)
- Authorization code:
 - The authorization code will be set to Null if one was previously provided but not this time.
- Comments
- Action:
 - Cancel
 - Update
 - Update and Dispatch
 - Deleting/cancelling can also be done at the line item level by setting all quantities to 0 and doing an update.
- Items (multiple):
 - Item ID (required)
 - Action (required)
 - * Update
 - * Delete
 - * Setting a quantity to 0 and using Update will be understood as a cancellation of that item.
 - * When deleting an item, the quantity will be set to 0, the item is not removed from the transaction
- Return Quantity (required):
 - Is supposed to be at the SUOM level
- Reason code:
 - These values need to match the SIM values

Web Service Output

- Return ID
 - If a new transfer ID is created, SIM sends the SIM transfer ID back.

Web Service Error Messages

Table A-86 Update Return Error Messages

ID	Event	Error Message Description	Result
1	Invalid Store	If Store ID is left empty, is not numeric, or the store cannot be found for the ID.	
2	Invalid return ID	If the ID of the return is left blank, is not numeric, or the return does not exist.	
3	Unable to lock return for update	If the Return is currently being modified by another user.	
5	Return ID is not provided and an update/dispatch is requested	If the action is UPDATE or UPDATE_AND_DISPATCH, and the return ID has not been included.	
6	User ID is not provided	If UpdateUser is not included in message.	
7	Invalid item action for transfer create	If request contained an action for an item other than update or delete.	
8	Invalid Item ID	No item was found for item identifier.	
9	Item ID missing	If item ID was not included in item level message.	
11	Item is not found	Item to update does not exist on the return.	
12	Return quantity is missing	If return quantity was not included in item level message.	
13	Return quantity is negative	If return quantity was a negative number.	
14	Return quantity is 0	All return quantities are 0 and user tries to dispatch	
15	Item quantity is a decimal value	In case the item quantity does not allow for decimals.	
16	Reason code is invalid	Reason code does not exist in SIM	
17	Authorization code is required	In case an authorization code is required and not provided and the action is dispatch or update dispatch.	
18	Not after Date has passed	It is not allowed to dispatch an RTW after the not after date has expired.	

Lookup Transfer Header

This Web service enables the user to find transfers that need to be executed.

SIM Inbound Information

- Store ID
- Other Store ID
- Status
- External ID
- Item ID
- Context type

SIM Outbound Information

Multiple transfers can be returned with the following info:

- Internal and external transfer ID
- Sending store ID and description

- Receiving store ID and description
- Status
- Last status date change
- Create user
- Approve user
- Receive user
- Number of line items

Fail Messages

- Invalid store ID
- Invalid status ID
- Invalid other store ID

This Web service must be able to support the following generic process:

1. User enters one or more elements of the above criteria to identify the transfer
2. SIM will return header transfer information
3. The external UI will use this information to allow the user to identify the specific transfer they want to work with.

Web Service Input

Calling attribute:

- Sending Location ID (required)
- Receiving location ID
- User ID
- Status:
 - Active
 - Active inbound
 - Active outbound
 - New
 - Pending_request
 - Awaiting response
 - Outbound reject
 - In progress
 - Inbound picking
 - In transit
 - Dispatched
 - Receiving
 - Closed
 - Received
 - Cancelled inbound

- Cancelled request
- Cancelled transfer
- Rejected
- Cancelled request
- External ID
- Item ID
- Context type
- Transfer ID
- From Date
- To Date

Web Service Output

- Transfer ID
- External transfer ID
- Sending Store ID
- Sending store description
- Receiving Store ID
- Receiving Store Description
- Status
- Status Date:
 - Last date Return changed status
- Create User
- Approval User
- Receive User
- Number of line items

Web Service Error Messages

Table A-87 Lookup Transfer Header Error Messages

ID	Event	Error Message Description	Result
1	Invalid Store	If Store ID is left empty or the store cannot be found for the ID	
2	Invalid other store	If the ID of the other store involved with the transfer is left blank, is not numeric, or does not exist.	
3	Invalid status	If the transfer status to query for is entered, but does not match a valid transfer status.	
4	Invalid external ID	If the External ID is not numeric.	
5	Invalid context type	If a context type does not exist for this code.	

Lookup Transfer Detail

This Web service will allow the user to receive detailed transfer information.

SIM Inbound Information

- Store ID
- Transfer ID

SIM Outbound Information

- Transfer ID
- Create store ID
- Sending and receiving store ID
- Sending and receiving store name
- External ID
- Status
- Create
- Update
- Approver
- Shipped
- Receive
- User and date
- Transfer & request comments
- Delivery slot ID
- Context type and value
- Item details

Fail Messages

- Invalid store ID
- Invalid transfer ID

This Web service must be able to support the following generic process:

1. The user selects a transfer ID
2. SIM will return all transfer information
3. The external UI will use this information to allow the user to add or change items and quantities as well as dispatch or create new transfers.

Web Service Input

Calling attribute:

- Location ID (required)
- Transfer ID (required)

Web Service Output

- Transfer ID
- Create Store ID
- Sending Store ID
- Sending Store Description
- Receiving Store ID
- Receiving Store Description
- External ID
- Status
- Create User
- Update User
- Approve User
- Shipped User
- Receive User
- Create Date
- Update Date
- Approval Date
- Ship Date
- Receive Date
- Transfer Comments
- Request Comments
- Delivery Slot ID
- Context type
- Context Value
- Item details (multiple):
 - Record ID
 - Item number
 - Item type
 - Short/long description
 - Department ID/Description
 - Class ID/Description
 - Subclass ID/Description
 - UOM
 - Case size
 - Requested Quantity
 - Approved Quantity
 - Transferred Quantity

- Received Quantity
- Damaged Quantity

Web Service Error messages

Table A-88 Lookup Transfer Detail Error Messages

ID	Event	Error Message Description	Result
1	Invalid Store	If Store ID is left empty, is not numeric, or the store cannot be found for the ID.	
2	Invalid transfer ID	If Transfer ID is left empty, is not numeric, or a transfer cannot be found for the ID.	

Update Transfer

This Web service enables the user to do several things:

- Make changes to items on a SIM transfer (add items or edit quantities)
- Create a new transfers
- Cancel transfers

SIM Inbound Information

- User ID
- Transfer ID
- Store ID
- Receiving store ID
- Action
- Items which each have a quantity and an action and quantity against them

SIM Outbound Information

Transfer ID

Fail Messages

- Invalid store ID
- Invalid other store ID
- Invalid transfer ID
- Transfer ID not null on create
- Transfer ID is not provided
- User not provided
- Invalid status

This Web service must be able to support the following generic process:

1. The user selects a transfer ID
2. SIM will return all transfer information
3. The external UI will use this information to allow the user to add or change items and quantities as well as dispatch or create new transfers.

Web Service Input

Calling attribute:

- Transfer ID
 - Required if existing transfer, empty if a new transfer is created
- User ID
- Shipping Store ID (required)
- Receiving Store ID (required)
- Action
 - Create
 - Create and Dispatch
 - Update
 - Update and Dispatch
 - Deleting/cancelling is done at the line item level by setting all quantities to 0 and doing an update.
- Items (multiple)
 - Item ID (required)
 - Action (required)
 - * Add
 - * Edit
 - * Setting a quantity to 0 and using edit will be understood as a cancellation of that item.
- Transfer Quantity (required)
 - Is supposed to be at the SUOM level

Web Service Output

- Transfer ID
 - If a new transfer ID is created, SIM will send the SIM transfer ID back.

Web Service Error Messages

Table A-89 Update Transfer Error Messages

ID	Event	Error Message Description	Result
1	Invalid Store	If Store ID is left empty, is not numeric, or the store cannot be found for the ID.	
2	Invalid transfer ID	If Transfer ID is left empty, is not numeric, or a transfer cannot be found for the ID.	
3	Invalid other store	If the ID of the other store involved with the transfer is left blank, is not numeric, does not exist or is not in the same transfer zone.	
4	Transfer ID is not null and the system is trying to create a new transfer. SIM is the owner of the IDs.	If the action is CREATE or CREATE_AND_DISPATCH, and the transfer ID has been included.	

Table A-89 (Cont.) Update Transfer Error Messages

ID	Event	Error Message Description	Result
5	Transfer ID is not provided and an update/dispatch is requested	If the action is UPDATE or UPDATE_AND_DISPATCH, and the transfer ID has not been included.	
6	User ID is not provided	If UpdateUser is not included in message.	
7	Invalid item action for transfer create	If request contained an action for an item other than ADD.	
8	Invalid Item ID	No item was found for item identifier or item added is a consignment/concession or non-inventory item.	
9	Item ID missing	If item ID was not included in item level message.	
10	Item is already on the transfer	Item to add to transfer already exists on transfer.	
11	Item is not found	Item to update does not exist on the transfer.	
12	Transfer quantity is missing	If transfer quantity was not included in item level message.	
13	Transfer quantity is negative	If transfer quantity was a negative number.	
14	Transfer quantity is 0	All transfer quantities are 0 and user tries to dispatch	
15	Item is not ranged	If the item being shipped is not ranged to you store or the sending store and the admin option: Allow non-ranged items is set to No.	
16	Invalid status	If the transfer is not in a valid status for update (must be In Progress)	
17	Transfer items not provided	If the incoming message for a transfer create did not have any items associated with it	

Lookup Markdowns

This Web service enables the user to find markdowns for a specific store.

SIM Inbound Information

- Store ID
- Date
- Price type
- Promotion ID
- Department ID
- Class ID
- Subclass ID
- Item ID
- Sequence ID

SIM Outbound Information

Multiple markdowns can come back:

- Item ID
- Item Type
- Short and long description

- Department ID and description
- Class ID and description
- Subclass ID and description
- Price type
- Current price
- Currency
- Selling UOM
- New Price
- current/new Multi Unit price
- UOM
- Currency

Fail Messages

- Invalid store ID
- Invalid markdown ID
- Invalid, department, class or subclass ID
- Invalid primary sequence ID
- Invalid Markdown ID

This Web service must be able to support the following generic process:

1. User scans a sequence.
2. SIM returns the items and their markdowns for that sequence.
3. User enters any of the above criteria.
4. SIM returns the proper markdowns.

Note: In case the markdown is already extracted, the current and new markdown is the same. Historic price information has not been made available yet in any Web service.

Web Service Input

Calling attribute:

- Location ID (required)
- Date
 - If not provided, tomorrow's dates are used
- Price Type
 - Permanent
 - Promotional
 - Clearance
- Promotion ID
- Department ID

- Class ID
- Subclass ID
- Item ID
- Sequence

Web Service Output

- Item ID
- Item Type
- Short Description
- Long Description
- Department Id
- Department description
- Class ID
- Class Description
- Subclass ID
- Subclass Description
- Price Type
 - Permanent, promotional, clearance
- Current Price
- Currency
- Current Selling UOM
- New Price
- New Selling UOM
- Current Multi Units
- Current Multi Unit Price
- Current Multi Unit UOM
- New Multi Units
- New Multi Unit Price
- New Multi Unit UOM

Web Service Error Messages

Table A-90 *Lookup Markdowns Error Messages*

ID	Event	Error Message Description	Result
1	Invalid Store	If Store ID is left empty or the store cannot be found for the ID	
2	Invalid Department	If the department ID is not decimal or does not exist	
3	Invalid Class	If the Class ID is not decimal or does not exist	
4	Invalid Subclass	If the Subclass ID is not decimal or does not exist	

Table A-90 (Cont.) Lookup Markdowns Error Messages

ID	Event	Error Message Description	Result
5	Invalid Promotion ID	If the promotion ID is not decimal or does not exist	
6	Invalid Markdown Sequence ID	If the Markdown sequence does not exist	
7	Invalid Markdown Date	If the date format is not valid	

Process Item Image

This Web service enables the user to send the item image information to SIM.

SIM Inbound Information

- Store ID
- Item ID
- Image Url
- Image Type
- Image Name
- Start Date
- End Date

SIM Outbound Information

- Status

Fail Messages

- Invalid Store ID
- Invalid Item ID

Web Service Input

Calling attribute:

- Store ID (required)
- Item ID (required)
- Image Url (required)
- Image Type (required)
- Image Name (required)
- Start Date
- End Date

Web Service Output

- Status
 - Success or Failure

Web Service Error messages**Table A-91 Process Item Image Error Messages**

ID	Event	Error Message Description	Result
1	Invalid Store ID	If Store ID is left empty, is not numeric, or the store cannot be found for the ID.	
2	Invalid Item ID	If the Item ID is left blank, is not numeric, or the item does not exist.	

Appendix: Code Examples

This appendix includes code samples referenced in [Example Code](#) in [Chapter 1](#), "[Customization](#)".

Example B-1 CustomSerialNumber

```
package oracle.retail.sim.closed.customuin;

import oracle.retail.sim.closed.business.BusinessObject;
import oracle.retail.sim.closed.common.BusinessException;
import oracle.retail.sim.closed.uin.UINStatus;
import org.apache.commons.lang.builder.EqualsBuilder;
import org.apache.commons.lang.builder.HashCodeBuilder;

/*
 * Copyright 2004, 2011, Oracle. All rights reserved.
 */
public class CustomSerialNumber extends BusinessObject {
    private static final long serialVersionUID = 7328521596108816814L;

    private Long id;
    private UINStatus status;

    public void setId(Long id) {
        if (id != null) {
            this.id = id;
        }
    }

    public Long getId() {
        return id;
    }

    public UINStatus getStatus() {
        return status;
    }

    public void setStatus(UINStatus status) throws BusinessException {
        checkForNullParameter("Status", status);
        executeRule("setStatus", status);
        this.status = status;
    }

    public boolean equals(Object object) {
        if (object == this) {
            return true;
        }
    }
}
```

```

    }
    if (object == null || object.getClass() != getClass()) {
        return false;
    }
    CustomSerialNumber other = (CustomSerialNumber) object;
    EqualsBuilder builder = new EqualsBuilder();
    builder.append(id, other.id);
    return builder.isEquals();
}

public int hashCode() {
    hashCodeBuilder builder = new hashCodeBuilder();
    builder.append(id);
    return builder.toHashCode();
}
}

```

Example B-2 CustomUINBean

```

package oracle.retail.sim.closed.ejb;

import javax.ejb.*;
import oracle.retail.sim.closed.abstractbean.AbstractSimServiceBean;
import oracle.retail.sim.closed.business.ServerServiceFactory;
import oracle.retail.sim.closed.logging.LogNames;
import oracle.retail.sim.closed.logging.LogService;
import oracle.retail.sim.closed.util.CompressedObject;
import oracle.retail.sim.closed.util.SimSession;
import oracle.retail.sim.closed.util.UniversalContext;

/**
 * Copyright 2004, 2011, Oracle. All rights reserved.
 */
@Stateless(mappedName = "CustomUINBean")
public class CustomUINBean extends AbstractSimServiceBean implements
CustomUINInterface {
    public CompressedObject moveSerialNumbersToInStock(CompressedObject
compressed0,
                                                    CompressedObject compressedSimSession) throws
Exception {
        long startTime = System.currentTimeMillis();
        if (LogService.isDebugEnabled(LogNames.SERVICE_TIMINGS)) {
            LogService.debug(LogNames.SERVICE_TIMINGS,
                "Starting service method:
CustomUINBean.moveSerialNumbersToInStock()");
        }
        try {
            java.util.List<oracle.retail.sim.closed.custom.CustomSerialNumber>
arg0 =
                (java.util.List<oracle.retail.sim.closed.custom.CustomSerialNumber>)
                    compressed0.recoverObject();
            UniversalContext.setSession((SimSession)
compressedSimSession.recoverObject());
            new CustomerUINServerServices().moveSerialNumbersToInStock(arg0);
            return new CompressedObject(null);
        } catch (Throwable t) {
            handleException(t, true);
            return null;
        } finally {
            completeServiceContext();
        }
    }
}

```

```

        long endTime = System.currentTimeMillis();
        if (LogService.isDebugEnabled(LogNames.SERVICE_TIMINGS)) {
            LogService.debug(LogNames.SERVICE_TIMINGS, "Took " + (endTime -
startTime)
                + "ms. for invocation of:
CustomUINBean.moveSerialNumbersToInStock()");
        }
    }
}
}

```

Example B-3 CustomUINCountTableEditor

```

package oracle.retail.sim.shared.swing.custom;

import java.awt.event.KeyEvent;
import java.awt.event.MouseAdapter;
import java.awt.event.MouseEvent;
import java.awt.event.MouseListener;
import javax.swing.JComponent;
import javax.swing.JTextField;
import oracle.retail.sim.closed.swing.table.SimPopupTableEditor;
import oracle.retail.sim.closed.swing.table.SimTableEditorEventAdaptor;
import oracle.retail.sim.closed.swing.table.SimTableEditorListener;
import oracle.retail.sim.closed.swing.tableeditor.PopupTableEditorListener;

/*****
*****
* Table editor that handles a boolean true/false value, displays a non-editable
check box.
* If the cell
* is clicked twice, a popup dialog is triggered and the data model is passed to
the dialog.
* <p>
* This is future work-in-progress code for future SIM 14.0 or later release.
* <p>
* Copyright 2004, 2011, Oracle. All rights reserved.
*****
*****/

public class CustomUINCountTableEditor extends JTextField implements
SimPopupTableEditor {
    private static final long serialVersionUID = -4236326754891359417L;

    private PopupTableEditorListener listener;
    private SimTableEditorEventAdaptor eventAdaptor;
    private Object model;

/*****
*****
* Constructors
*****
*****/

    public CustomUINCountTableEditor(PopupTableEditorListener listener) {
        eventAdaptor = new SimTableEditorEventAdaptor(this);
    }
}

```

```

        addMouseListener(buildMouseListener());
        setHorizontalAlignment(RIGHT);
        setOpaque(true);
        setEnabled(false);
        setListener(listener);
    }

/*****
*****
* Basic Property Methods of a Table Editor
*****
*****/

    public Class getValueClass() {
        return Integer.class;
    }

    public void setValueClass(Class valueClass) {
        // Ignore
    }

    public void setModel(Object model) {
        this.model = model;
    }

    public JComponent getComponent() {
        return this;
    }

    private void setListener(PopupTableEditorListener listener) {
        this.listener = listener;
    }

    public void setCoordinates(int row, int column) {
        // Ignore
    }

/*****
*****
* Get, Set and Check the data value of the editor
*****
*****/

    public Object getValue() {
        return getText();
    }

    public void setValue(Object value) {
        if (value != null) {
            setText(value.toString());
            popupDialog();
        }
    }

    public boolean checkValue() {
        return true;
    }

```

```

    }

/*****
*****
 * Table Editor Listener
*****
*****/

    public void addTableEditorListener(SimTableEditorListener listener) {
        eventAdaptor.addTableEditorListener(listener);
    }

    public void removeTableEditorListener(SimTableEditorListener listener) {
        eventAdaptor.removeTableEditorListener(listener);
    }

/*****
*****
 * Determines if keystroke is invalid for field. Always false for a boolean
editor.
*****
*****/

    public boolean isInvalidKeystroke(KeyEvent event) {
        return false;
    }

/*****
*****
 * Mouse Listener That Pops The Dialog
*****
*****/

    private MouseListener buildMouseListener() {
        return new MouseAdapter() {
            public void mouseClicked(MouseEvent event) {
                if (event.getClickCount() == 2) {
                    popupDialog();
                }
            }
        };
    }

/*****
*****
 * Display Dialog
*****
*****/

    private void popupDialog() {
        if (listener != null) {
            listener.popupDialog(model);

            CustomUINCreateWrapper wrapper = (CustomUINCreateWrapper) model;

```

```

        setText(String.valueOf(wrapper.getSerialNumberCount()));
    }
}

```

Example B-4 CustomUINCreateDialog

```

package oracle.retail.sim.shared.swing.custom;

import java.awt.GridBagLayout;
import java.util.Collections;
import java.util.List;
import java.util.Set;
import oracle.retail.sim.closed.application.Application;
import oracle.retail.sim.closed.common.ErrorKey;
import oracle.retail.sim.closed.simclient.util.SimClientErrorKey;
import oracle.retail.sim.closed.swing.dialog.RDialog;
import oracle.retail.sim.closed.swing.displayer.AttributeDisplayer;
import oracle.retail.sim.closed.swing.editor.RDisplayLabelEditor;
import oracle.retail.sim.closed.swing.event.RActionEvent;
import oracle.retail.sim.closed.swing.event.REventListener;
import oracle.retail.sim.closed.swing.panel.RPanel;
import oracle.retail.sim.closed.swing.table.SimTable;
import oracle.retail.sim.closed.swing.table.SimTableAttribute;
import oracle.retail.sim.closed.swing.table.SimTableDefinition;
import oracle.retail.sim.closed.swing.table.SimTableEditorEvent;
import oracle.retail.sim.closed.swing.table.SimTableEditorListener;
import oracle.retail.sim.closed.swing.table.SimTablePane;
import oracle.retail.sim.closed.swing.table.SimTableSortAttribute;
import oracle.retail.sim.closed.swing.util.GridTool;
import oracle.retail.sim.closed.swing.util.UIException;
import oracle.retail.sim.closed.swing.widget.RButton;
import oracle.retail.sim.closed.uin.SerialNumberValue;
import oracle.retail.sim.closed.uin.UINStatus;
import oracle.retail.sim.closed.util.CollectionUtil;
import oracle.retail.sim.shared.swing.core.SimNavigation;
import oracle.retail.sim.shared.swing.uin.SerialNumberProperty;
import oracle.retail.sim.shared.swing.uin.SerialNumberWrapper;

/*****
*****
* This dialog handles entering UIN information for line item from the main UIN
Create screen.
* <p>
* This is future work-in-progress code for future SIM 14.0 or later release.
* <p>
* Copyright 2004, 2011, Oracle. All rights reserved.
*****
*****/

public class CustomUINCreateDialog extends RDialog implements REventListener {
    private static final long serialVersionUID = -7885503433032637549L;

    private CustomUINCreateDialogModel model = new CustomUINCreateDialogModel();

    private RDisplayLabelEditor itemEditor = new RDisplayLabelEditor("Item");
    private RDisplayLabelEditor itemDescEditor = new RDisplayLabelEditor("Item
Description");

```

```

        private CustomUINCreateDialogTableEditor serialNumberEditor
                                   = new
CustomUINCreateDialogTableEditor();

        private SimTable serialNumberTable = new SimTable(new
CreateUINTableDefinition());
        private SimTablePane serialNumberTablePane = new
SimTablePane(serialNumberTable);

        private RButton doneButton = new RButton(SimNavigation.DONE);
        private RButton addButton = new RButton(SimNavigation.ADD);
        private RButton deleteButton = new RButton(SimNavigation.DELETE);
        private RButton cancelButton = new RButton(SimNavigation.CANCEL);

/*****
*****
* Build Dialog
*****
*****/
    public CustomUINCreateDialog() {
        super(Application.getFrame());
        setStatusBarVisible(false);
        setTitle("UIN");
        setSize(550, 400);
        initializeWidgets();
        layoutContent();
        centerWindow();
    }

    private void initializeWidgets() {
serialNumberEditor.addTableEditorListener(buildSerialNumberValueListener());

        serialNumberTable.setMultipleRowSelectionMode();

        doneButton.registerAction(this, SimNavigation.DONE);
        addButton.registerAction(this, SimNavigation.ADD);
        deleteButton.registerAction(this, SimNavigation.DELETE);
        cancelButton.registerAction(this, SimNavigation.CANCEL);
    }

    private void layoutContent() {
        addButton(doneButton);
        addButton(addButton);
        addButton(deleteButton);
        addButton(cancelButton);

        RPanel headerPanel = new RPanel(new GridBagLayout());
        headerPanel.add(itemEditor, GridTool.constraints(0, 0, 1, 1, 1, 0, 0, 3,
3, 0, 0, 10));
        headerPanel.add(itemDescEditor, GridTool.constraints(1, 0, 1, 1, 1, 0, 0,
3, 3, 0, 0, 0));

        RPanel mainPanel = new RPanel(new GridBagLayout());
        mainPanel.add(headerPanel, GridTool.constraints(0, 0, 1, 1, 1, 0, 0, 3, 0,
0, 5, 0));
        mainPanel.add(serialNumberTablePane, GridTool.constraints(0, 1, 1, 1, 1,
1, 0, 3, 0, 0, 0, 0));

```

```

        setContentPane(mainPanel);
    }

    /**
     * Build Dialog
     */

    public void setWrapper(CustomUINCreateWrapper wrapper) {
        model.setWrapper(wrapper);
        try {
            itemEditor.setData(model.getItemId());
            itemDescEditor.setData(model.getItemDescription());
            serialNumberTable.setRows(model.getSerialNumberWrappers());
        } catch (Throwable exception) {
            displayException(exception);
        }
    }

    /**
     * Listen to serial number entry field in order to validate UIN entered
     */

    private SimTableEditorListener buildSerialNumberValueListener() {
        return new SimTableEditorListener() {
            public void performTableEditorEvent(SimTableEditorEvent event) {
                if (event.isFocusLostEvent()) {
                    Set<String> serialNumberSet = CollectionUtil.newHashSet();
                    List<SerialNumberWrapper> wrappers =
serialNumberTable.getAllRowData();
                    for (SerialNumberWrapper wrapper : wrappers) {
                        SerialNumberValue serialNumber =
wrapper.getSerialNumberValue();
                        if (serialNumber != null) {
                            if (serialNumberSet.contains(serialNumber.getUin())) {
                                serialNumberTable.removeRow(wrapper);
                                displayException(
                                    new UIException(ErrorKey.UIN_DUPLICATE_
ERROR_PC));
                                continue;
                            }
                            if (serialNumber.getStatus() != UINStatus.UNCONFIRMED)
{
                                serialNumberTable.removeRow(wrapper);
                                displayException(new UIException(
                                    "Serial Number already
exists!"));
                                continue;
                            }
                            serialNumberSet.add(serialNumber.getUin());
                        }
                    }
                }
            }
        }
    }

```

```

// Temporary fix - only add the new row if the button panel
does not have
    if (isMouseOverButton()) {
        return;
    }
    try {
        doAddRow();
    } catch (Throwable exception) {
        displayException(exception);
    }
}
};
}

/*****
*****
* Handle Actions
*****
*****/
public void performActionEvent(RActionEvent event) {
    String command = event.getEventCommand();
    try {
        if (command.equals(SimNavigation.DONE)) {
            doDone();
        } else if (command.equals(SimNavigation.ADD)) {
            doAddRow();
        } else if (command.equals(SimNavigation.DELETE)) {
            doDeleteRow();
        } else if (command.equals(SimNavigation.CANCEL)) {
            doCancel();
        }
    } catch (Throwable exception) {
        displayException(exception);
    }
}

/*****
*****
* Add Action
*****
*****/

private void doAddRow() {
    serialNumberTable.stopEditing();
    List<SerialNumberWrapper> wrappers = serialNumberTable.getAllRowData();
    for (SerialNumberWrapper wrapper : wrappers) {
        if (wrapper.getSerialNumberValue() == null) {
            return;
        }
    }
    serialNumberTable.addRow(model.createSerialNumberWrapper());
    serialNumberTable.editCellInLastRow(SerialNumberProperty.SERIAL_NUMBER);
}

```

```

/*****
*****
* Delete Action

*****/

    private void doDeleteRow() throws Exception {
        List<SerialNumberWrapper> selectedWrappers =
serialNumberTable.getAllSelectedRowData();
        if (selectedWrappers.isEmpty()) {
            throw new UIException(SimClientErrorKey.NO_ROWS_SELECTED_DELETE);
        }
        for (SerialNumberWrapper wrapper : selectedWrappers) {
            serialNumberTable.removeRow(wrapper);
        }
        serialNumberTable.refreshTable();
    }

/*****
*****
* Done Action

*****/

    private void doDone() throws Exception {
        serialNumberTable.stopEditing();
        List<SerialNumberWrapper> wrappers = serialNumberTable.getAllRowData();
        model.saveSerialNumbers(wrappers);
        closeWindow();
    }

/*****
*****
* Override method to alter functionality. Default stops editing and closes
window.

*****/

    private void doCancel() {
        serialNumberTable.stopEditing();
        closeWindow();
    }

/*****
*****
* UIN Table Definition

*****/

    private class CreateUINTableDefinition extends SimTableDefinition {

        public Class getDataClass() {
            return SerialNumberWrapper.class;
        }
    }

```

```

        public List<SimTableSortAttribute> getSortAttributes() {
            return Collections.singletonList(new
SimTableSortAttribute("serialNumberValue"));
        }

        public List<SimTableAttribute> getAttributes() {
            List<SimTableAttribute> attributes = CollectionUtil.newArrayList(1);
            attributes.add(new SimTableAttribute(model.getUILabel(),
"serialNumberValue",
                new AttributeDisplayer("uin"), serialNumberEditor));
            return attributes;
        }
    }
}

```

Example B-5 CustomUINCreateDialogModel

```

package oracle.retail.sim.shared.swing.custom;

import java.util.List;
import oracle.retail.sim.closed.business.FunctionalArea;
import oracle.retail.sim.closed.uin.SerialNumberValue;
import oracle.retail.sim.closed.uin.UINType;
import oracle.retail.sim.closed.util.CollectionUtil;
import oracle.retail.sim.closed.util.RkConfigManager;
import oracle.retail.sim.shared.swing.core.SimScreenModel;
import oracle.retail.sim.shared.swing.uin.SerialNumberWrapper;

/*****
*****
* The business logic model for the Custom UIN Create Dialog.
* <p>
* This is future work-in-progress code for future SIM 14.0 or later release.
* <p>
* Copyright 2004, 2011, Oracle. All rights reserved.
*****
*****/

public class CustomUINCreateDialogModel extends SimScreenModel {

    private CustomUINCreateWrapper lineItemWrapper;

    public void setWrapper(CustomUINCreateWrapper wrapper) {
        lineItemWrapper = wrapper;
    }

    public String getItemId() {
        if (lineItemWrapper != null) {
            return lineItemWrapper.getStockItem().getId();
        }
        return null;
    }

    public String getItemDescription() {
        if (lineItemWrapper != null) {
            if (RkConfigManager.isItemShortDescription()) {
                return lineItemWrapper.getStockItem().getShortDescription();
            }
        }
    }
}

```

```

        return lineItemWrapper.getStockItem().getLongDescription();
    }
    return null;
}

public List<SerialNumberWrapper> getSerialNumberWrappers() {
    List<SerialNumberWrapper> wrappers = CollectionUtil.newArrayList();
    for (SerialNumberValue value : lineItemWrapper.getSerialNumbers()) {
        SerialNumberWrapper wrapper = createSerialNumberWrapper();
        wrapper.setSerialNumberValue(value);
        wrapper.setDefaultAction();
        wrapper.setValidated();

        wrappers.add(wrapper);
    }
    if (wrappers.isEmpty()) {
        wrappers.add(createSerialNumberWrapper());
    }
    return wrappers;
}

public SerialNumberWrapper createSerialNumberWrapper() {
    return new SerialNumberWrapper(FunctionalArea.MANUAL,
        lineItemWrapper.getStockItem().getId(), getUINType(),
getUINLabel());
}

public UINType getUINType() {
    if (lineItemWrapper != null) {
        return lineItemWrapper.getStockItem().getUINType();
    }
    return UINType.SERIAL;
}

public String getUINLabel() {
    if (lineItemWrapper != null) {
        return lineItemWrapper.getStockItem().getUINLabel();
    }
    return null;
}

public void saveSerialNumbers(List<SerialNumberWrapper> wrappers) {
    List<SerialNumberValue> serialNumbers = CollectionUtil.newArrayList();
    for (SerialNumberWrapper wrapper : wrappers) {
        SerialNumberValue value = wrapper.getSerialNumberValue();
        if (value != null) {
            serialNumbers.add(value);
        }
    }
    lineItemWrapper.setSerialNumbers(serialNumbers);
}
}

```

Example B-6 CustomUINCreateDialogTableEditor

```

package oracle.retail.sim.shared.swing.custom;

import java.awt.event.FocusEvent;
import java.awt.event.FocusListener;
import java.awt.event.KeyEvent;

```

```

import javax.swing.JComponent;
import oracle.retail.sim.closed.application.Application;
import oracle.retail.sim.closed.business.ClientServiceFactory;
import oracle.retail.sim.closed.business.FunctionalArea;
import oracle.retail.sim.closed.common.BusinessException;
import oracle.retail.sim.closed.common.ErrorKey;
import oracle.retail.sim.closed.common.locale.StringConstants;
import oracle.retail.sim.closed.common.type.AbstractDisplayer;
import oracle.retail.sim.closed.locale.StringUtility;
import oracle.retail.sim.closed.locale.Translator;
import oracle.retail.sim.closed.simclient.util.SimClientErrorKey;
import oracle.retail.sim.closed.swing.dialog.RErrorDialog;
import oracle.retail.sim.closed.swing.displayer.AttributeDisplayer;
import oracle.retail.sim.closed.swing.logging.UILog;
import oracle.retail.sim.closed.swing.sim.SimRepository;
import oracle.retail.sim.closed.swing.table.SimTable;
import oracle.retail.sim.closed.swing.table.SimTableEditor;
import oracle.retail.sim.closed.swing.table.SimTableEditorEventAdaptor;
import oracle.retail.sim.closed.swing.table.SimTableEditorListener;
import oracle.retail.sim.closed.swing.util.UIErrorKey;
import oracle.retail.sim.closed.swing.util.UIExceptionFactory;
import oracle.retail.sim.closed.swing.widget.RTextField;
import oracle.retail.sim.closed.uin.SerialNumberValue;
import oracle.retail.sim.shared.swing.core.SimName;
import oracle.retail.sim.shared.swing.uin.SerialNumberWrapper;

/*****
*****
* Table Editor for editing a CustomerSerialNumber business object. The model for
the table
* row that uses this editor
* must be a UINWrapper.
* <p>
* This is future work-in-progress code for future SIM 14.0 or later release.
* <p>
* Copyright 2004, 2011, Oracle. All rights reserved.
*****
*****/

public class CustomUINCreateDialogTableEditor extends RTextField
                                                implements SimTableEditor,
FocusListener {
    private static final long serialVersionUID = -1463881160730583097L;

    private AbstractDisplayer displayer;
    private SimTableEditorEventAdaptor eventAdaptor;
    private SerialNumberWrapper wrapper;
    private SerialNumberValue serialNumberValue;
    private String lastCheckedSerialNumber = StringConstants.EMPTY;
    private FocusEvent lastFocusEvent;
    private boolean isErrorState;
    private int row = -1;
    private int column = -1;

    public CustomUINCreateDialogTableEditor() {
        eventAdaptor = new SimTableEditorEventAdaptor(this);
        displayer = new AttributeDisplayer("uin");
        setIdentifier(SimName.SERIAL_NUMBER);
        setMargin(null);
    }

```

```

        setBorder(null);
        addFocusListener(this);
    }

    public Class getValueClass() {
        return SerialNumberValue.class;
    }

    public void setValueClass(Class valueClass) {
        // Ignore
    }

    public void setModel(Object model) {
        wrapper = (SerialNumberWrapper) model;
    }

/*****
*****
* Assign coordinates to the editor.
*****
*****/
    public void setCoordinates(int row, int column) {
        this.row = row;
        this.column = column;
    }

/*****
*****
* Reactivate editing within the table cell.
*****
*****/
    private void reactivateEditing(Object object) {
        if (object instanceof SimTable) {
            SimTable table = (SimTable) object;
            try {
                if (table.getSelectedRow() != row) {
                    table.setRowSelectionInterval(row, row);
                }
                table.editCellAt(row, column);
            } catch (Throwable ex) {
                UILog.debug(getClass(), ex.getMessage());
            }
        }
    }

    public Object getValue() {
        if (isErrorState()) {
            return null;
        }
        return serialNumberValue;
    }

    public void setData(Object value) {
        if (value instanceof SerialNumberValue) {
            setValue(value);
            return;
        }
    }

```

```

    }
    throw new IllegalArgumentException(
        "CustomSerialNumberTableEditor only edits
UINValue!");
    }

    public void setValue(Object value) {
        if (value instanceof String) {
            setText((String) value);
            checkValue();
        } else if (value instanceof SerialNumberValue) {
            serialNumberValue = (SerialNumberValue) value;
            setText(displayer.getDisplayText(serialNumberValue));
        } else if (value == null) {
            serialNumberValue = null;
            clear();
        }
        eventAdaptor.fireTypeEditorEvent();
    }

    public JComponent getComponent() {
        return this;
    }

    public boolean checkValue() {
        String enteredSerialNumber = getText();

        setErrorState(false);

        if (StringUtil.isNullOrEmpty(enteredSerialNumber)) {
            if (serialNumberValue == null) {
                return true;
            }
            displayErrorWithReset(SimClientErrorKey.ITEM_BLANK_ERROR);
            return false;
        }

        try {
            if (serialNumberValue != null
                && enteredSerialNumber.equals(serialNumberValue.getUin())
                && enteredSerialNumber.equals(lastCheckedSerialNumber)) {
                return true;
            }
            SerialNumberValue tempValue =
ClientServiceFactory.getUINServices().findSerialNumberValueOrCreate(
                SimRepository.getStoreId(), wrapper.getItemId(),
enteredSerialNumber,
                wrapper.getType(), FunctionalArea.MANUAL);
            if (tempValue == null) {
                String message = Translator.getMessage(ErrorKey.UIN_NOT_FOUND_FOR_
ITEM,
                wrapper.getType().getDescription(), enteredSerialNumber,
wrapper.getItemId());
                displayErrorWithReset(message);
                return false;
            }
            serialNumberValue = tempValue;
            lastCheckedSerialNumber = enteredSerialNumber;
            return true;
        }
    }

```

```

        } catch (BusinessException businessException) {

displayError(UIExceptionFactory.buildError(businessException).getLocalizedMessage(
));
        } catch (Throwable t) {
            displayError(UIErrorKey.DEFAULT_FATAL_DIALOG_MESSAGE);
        }
        lastCheckedSerialNumber = StringConstants.EMPTY;
        serialNumberValue = null;
        clear();
        return false;
    }

/*****
*****
* Add Remove Table Editor Listeners
*****
*****/

    public void addTableEditorListener(SimTableEditorListener listener) {
        eventAdaptor.addTableEditorListener(listener);
    }

    public void removeTableEditorListener(SimTableEditorListener listener) {
        eventAdaptor.removeTableEditorListener(listener);
    }

/*****
*****
* Error State
*****
*****/

    protected void setErrorState(boolean errorState) {
        isErrorState = errorState;
    }

    protected boolean isErrorState() {
        return isErrorState;
    }

/*****
*****
* Determines if keystroke is invalid for input into the field.
*****
*****/

    public boolean isInvalidKeystroke(KeyEvent event) {
        return false;
    }

/*****
*****
* Implement the focus listener methods to call do value modified when focus is
lost.

```

```

*****
*****/
    public void focusGained(FocusEvent event) {
    }

    public void focusLost(FocusEvent event) {
        if (event.isTemporary()) {
            return;
        }
        if (event != lastFocusEvent) {
            lastFocusEvent = event;
            if (checkValue()) {
                eventAdaptor.fireTypeEditorEvent(true);
                return;
            }
            reactivateEditing(event.getOppositeComponent());
        }
    }
}

/*****
*****
* Display Error Methods
*****
*****/

    protected void displayErrorWithReset(String message) {
        if (displayer != null) {
            setText(displayer.getDisplayText(serialNumberValue));
        }
        setErrorState(true);
        displayError(message);
    }

    protected void displayError(String message) {
        RErrorDialog dialog = new RErrorDialog(Application.getFrame());
        dialog.setTitle("Table Editor Error");
        dialog.setMessage(message);
        dialog.activate();
    }
}

```

Example B-7 CustomUINCreateModel

```

package oracle.retail.sim.shared.swing.custom;

import java.util.List;
import oracle.retail.sim.closed.application.RepositoryManager;
import oracle.retail.sim.closed.custom.CustomSerialNumber;
import oracle.retail.sim.closed.custom.CustomUINEJBServices;
import oracle.retail.sim.closed.uin.SerialNumberValue;
import oracle.retail.sim.closed.util.CollectionUtil;
import oracle.retail.sim.shared.swing.core.SimScreenModel;

/*****
*****
* Model for the Create UIN entry screen.
* <p>

```

```

* This is future work-in-progress code for future SIM 14.0 or later release.
* <p>
* Copyright 2004, 2011, Oracle. All rights reserved.

*****
*****/

public class CustomUINCreateModel extends SimScreenModel {

    private String CUSTOM_UIN_SERVICES_KEY = "CUSTOM_UIN_SERVICES_KEY";

    public void saveSerialNumbers(List<CustomUINCreateWrapper> wrappers) throws
Exception {
        List<CustomSerialNumber> serialNumbers = CollectionUtil.newArrayList();
        for (CustomUINCreateWrapper wrapper : wrappers) {
            for (SerialNumberValue serialNumberValue : wrapper.getSerialNumbers())
            {
                CustomSerialNumber serialNumber = new CustomSerialNumber();
                serialNumber.setId(serialNumberValue.getUINDetailId());
                serialNumber.setStatus(serialNumberValue.getStatus());
                serialNumbers.add(serialNumber);
            }
        }
        getCustomUINService().moveSerialNumbersToInStock(serialNumbers);
    }

    private CustomUINEJBServices getCustomUINService() {
        CustomUINEJBServices services = (CustomUINEJBServices)
RepositoryManager.getStateObject(CUSTOM_UIN_SERVICES_
KEY);
        if (services == null) {
            services = new CustomUINEJBServices();
            RepositoryManager.addStateObject(CUSTOM_UIN_SERVICES_KEY, services);
        }
        return services;
    }
}

```

Example B-8 CustomUINCreatePanel

```

package oracle.retail.sim.shared.swing.custom;

import java.util.Collections;
import java.util.List;
import java.util.Set;
import oracle.retail.sim.closed.item.StockItem;
import oracle.retail.sim.closed.swing.displayer.AttributeDisplayer;
import oracle.retail.sim.closed.swing.displayer.IntegerDisplayer;
import oracle.retail.sim.closed.swing.event.RActionEvent;
import oracle.retail.sim.closed.swing.event.REventListener;
import oracle.retail.sim.closed.swing.frame.ScreenPanel;
import oracle.retail.sim.closed.swing.table.SimTable;
import oracle.retail.sim.closed.swing.table.SimTableAttribute;
import oracle.retail.sim.closed.swing.table.SimTableDefinition;
import oracle.retail.sim.closed.swing.table.SimTableEditorEvent;
import oracle.retail.sim.closed.swing.table.SimTableEditorListener;
import oracle.retail.sim.closed.swing.table.SimTablePane;
import oracle.retail.sim.closed.swing.tableeditor.PopupTableEditorListener;
import oracle.retail.sim.closed.util.CollectionUtil;
import oracle.retail.sim.shared.swing.uom.StockItemTableEditor;

```

```

/*****
*****
* UIN Create Panel - Contains the visual elements of the UIN Create screen.
* <p>
* This is future work-in-progress code for future SIM 14.0 or later release.
* <p>
* Copyright 2004, 2011, Oracle. All rights reserved.
*****
*****/

public class CustomUINCreatePanel extends ScreenPanel implements REventListener {
    private static final long serialVersionUID = 7667002106326748099L;

    private CustomUINCreateModel model = new CustomUINCreateModel();

    private StockItemTableEditor stockItemTableEditor = new
StockItemTableEditor();

    private SimTable stockItemTable = new SimTable(new
CustomCreateUINTableDefinition());
    private SimTablePane stockItemPane = new SimTablePane(stockItemTable);

/*****
*****
* Initialize Panel
*****
*****/

    public CustomUINCreatePanel() {
        initializePanel();
        layoutPanel();
    }

    private void initializePanel() {
        stockItemTableEditor.addTableEditorListener(buildStockItemListener());
        stockItemTable.setColumnSize("serialNumberCount", SimTable.LABEL_WIDTH);
    }

    private void layoutPanel() {
        setContentPane(stockItemPane);
    }

    public boolean isStartable() {
        return true;
    }

    public void start() throws Throwable {
        stockItemTable.addRow(new CustomUINCreateWrapper());
    }

    public void stop() {
    }

    public void performActionEvent(RActionEvent event) {
    }
}

```

```

/*****
*****
* Handle Add Item Action

*****/

    public void doAddItem() {
        List<CustomUINCreateWrapper> wrappers = stockItemTable.getAllRowData();
        for (CustomUINCreateWrapper wrapper : wrappers) {
            if (wrapper.getStockItem() == null) {
                return;
            }
        }
        stockItemTable.addRow(new CustomUINCreateWrapper());
    }

/*****
*****
* Handle Delete Item Action

*****/

    public void doDeleteItem() {
        List<CustomUINCreateWrapper> wrappers =
stockItemTable.getAllSelectedRowData();
        for (CustomUINCreateWrapper wrapper : wrappers) {
            stockItemTable.removeRow(wrapper);
        }
    }

/*****
*****
* Handle Done Action

*****/

    public void doHandleDone() throws Exception {
        List<CustomUINCreateWrapper> wrappers = stockItemTable.getAllRowData();
        model.saveSerialNumbers(wrappers);
    }

/*****
*****
* Stock Item Listener - Accessed when stock item is added to table of items.

*****/

    private SimTableEditorListener buildStockItemListener() {
        return new SimTableEditorListener() {
            public void performTableEditorEvent(SimTableEditorEvent event) {
                Set<StockItem> stockItems = CollectionUtil.newHashSet();
                List<CustomUINCreateWrapper> wrappers =

```

```

stockItemTable.getAllSelectedRowData();
    for (CustomUINCreateWrapper wrapper : wrappers) {
        if (stockItems.contains(wrapper.getStockItem())) {
            displayError("Duplicate item has been added.");
            stockItemTable.removeRow(wrapper);
            return;
        }
        stockItems.add(wrapper.getStockItem());
    }
}
};
}

/*****
*****
* Table Definition
*****
*****/

private class CustomCreateUINTableDefinition extends SimTableDefinition {

    public Class getDataClass() {
        return CustomUINCreateWrapper.class;
    }

    public List<String> getOverrideEditableAttributes() {
        return Collections.singletonList(CustomUINCreateWrapper.UIN_COUNT_
PROPERTY);
    }

    public List<SimTableAttribute> getAttributes() {
        List<SimTableAttribute> attributes = CollectionUtil.newArrayList(3);
        attributes.add(new SimTableAttribute("Item",
CustomUINCreateWrapper.STOCK_ITEM_PROPERTY, new
AttributeDisplayer("id"),
stockItemTableEditor));
        attributes.add(new SimTableAttribute("Item Description",
CustomUINCreateWrapper.DESCRPTION_PROPERTY));
        attributes.add(new SimTableAttribute("UIN Qty",
CustomUINCreateWrapper.UIN_COUNT_PROPERTY, new
IntegerDisplayer(),
new CustomUINCountTableEditor(new UINPopupListener())));
        return attributes;
    }
}

/*****
*****
* UIN POPUP LISTENER - Pops up when UIN column is double-clicked.
*****
*****/

private class UINPopupListener implements PopupTableEditorListener {
    public void popupDialog(Object lineItem) {
        CustomUINCreateDialog dialog = new CustomUINCreateDialog();
        dialog.setWrapper((CustomUINCreateWrapper) lineItem);
    }
}

```

```

        dialog.setVisible(true);
        stockItemTable.setRows(stockItemTable.getAllRowData());
    }
}

```

Example B-9 CustomUINCreateScreen

```

package oracle.retail.sim.shared.swing.custom;

import oracle.retail.sim.closed.application.NavigationEvent;
import oracle.retail.sim.closed.swing.sim.SimScreen;
import oracle.retail.sim.shared.swing.core.SimNavigation;

/*****
*****
* UIN Create Screen - This screens provides the ability to create and insert new
UINs into
* SIM without validation or generating matching transactions. This should be used
exclusively
* to dataseed UINs into the application.
* <p>
* This is future work-in-progress code for future SIM 14.0 or later release.
* <p>
* Copyright 2004, 2011, Oracle. All rights reserved.
*****
*****/

public class CustomUINCreateScreen extends SimScreen {
    private static final long serialVersionUID = 487712289865375658L;

    private CustomUINCreatePanel panel = new CustomUINCreatePanel();

    public CustomUINCreateScreen() {
        add(panel);
    }

/*****
*****
* Screen Methods
*****
*****/

    public String getScreenName() {
        return "UIN Create";
    }

    public boolean isStartable() {
        return panel.isStartable();
    }

    public void start() throws Throwable {
        showMenu();
        panel.start();
    }

    public void stop() {

```

```

        panel.stop();
    }

/*****
*****
* Handle Navigation Events
*****
*****/

public void navigationEvent(NavigationEvent event) {
    String command = event.getCommand();
    try {
        if (command.equals(SimNavigation.ADD_ITEM)) {
            panel.doAddItem();
        } else if (command.equals(SimNavigation.DELETE_ITEM)) {
            panel.doDeleteItem();
        } else if (command.equals(SimNavigation.DONE)) {
            panel.doHandleDone();
        }
    } catch (Throwable exception) {
        displayException(panel, event, exception);
    }
}
}

```

Example B-10 CustomUINCreateWrapper

```

package oracle.retail.sim.shared.swing.custom;

import java.util.List;
import oracle.retail.sim.closed.common.BusinessException;
import oracle.retail.sim.closed.common.locale.StringConstants;
import oracle.retail.sim.closed.item.StockItem;
import oracle.retail.sim.closed.uin.SerialNumberValue;
import oracle.retail.sim.closed.util.CollectionUtil;
import oracle.retail.sim.closed.util.RkConfigManager;

/*****
*****
* Wrapper for single entry row in the serial number table.
* <p>
* This is future work-in-progress code for future SIM 14.0 or later release.
* <p>
* Copyright 2004, 2011, Oracle. All rights reserved.
*****
*****/

public class CustomUINCreateWrapper {

    public static final String STOCK_ITEM_PROPERTY = "stockItem";
    public static final String DESCRIPTION_PROPERTY = "description";
    public static final String UIN_COUNT_PROPERTY = "serialNumberCount";

    private StockItem stockItem;
    private List<SerialNumberValue> serialNumbers = CollectionUtil.newArrayList();

    public StockItem getStockItem() {

```

```

        return stockItem;
    }

    public String getDescription() {
        if (stockItem == null) {
            return StringConstants.EMPTY;
        }
        if (RkConfigManager.isItemShortDescription()) {
            return stockItem.getShortDescription();
        }
        return stockItem.getLongDescription();
    }

    public void setStockItem(StockItem stockItem) throws BusinessException {
        if (stockItem != null && !stockItem.isSerialNumberRequired()) {
            throw new BusinessException("Item does not support serial numbers.");
        }
        this.stockItem = stockItem;
    }

    public Integer getSerialNumberCount() {
        return serialNumbers.size();
    }

    public List<SerialNumberValue> getSerialNumbers() {
        return serialNumbers;
    }

    public void setSerialNumbers(List<SerialNumberValue> serialNumbers) {
        if (serialNumbers != null) {
            this.serialNumbers = serialNumbers;
        }
    }

    public boolean isPropertyModifiable(String property) {
        if (property.equals(STOCK_ITEM_PROPERTY)) {
            return stockItem == null;
        }
        if (property.equals(UIN_COUNT_PROPERTY)) {
            return true;
        }
        return false;
    }
}

```

Example B-11 CustomUINDataBean

```

package oracle.retail.sim.shared.dataaccess.databean.generated;

import java.sql.ResultSet;
import java.sql.SQLException;
import java.sql.Types;
import java.util.ArrayList;
import java.util.List;
import oracle.retail.sim.closed.dataaccess.FullDataBean;

/**
 *
 * This class is an object representation of the database table UIN_DETAIL<BR>
 * Followings are the column of the table: <BR>

```

```

*      ID(PK) -- NUMERIC(12)<BR>
*      STORE_ID -- NUMERIC(10)<BR>
*      STATUS -- NUMERIC(2)<BR>
*
* Copyright 2004, 2011, Oracle. All rights reserved.
*/
public class CustomUinDataBean extends FullDataBean<CustomUinDataBean> {
    private static String getSelectSqlText() {
        return "select ID, STORE_ID, STATUS from UIN_DETAIL ";
    }

    private static String getInsertSqlText() {
        return "insert into UIN_DETAIL (ID, STORE_ID, STATUS) values (?, ?, ?)";
    }

    private static String getUpdateSqlText() {
        return "update UIN_DETAIL set STORE_ID = ?, STATUS = ? ";
    }

    private static String getDeleteSqlText() {
        return "delete from UIN_DETAIL ";
    }

    public static final String TABLE_NAME = "UIN_DETAIL";
    public static final String COL_ID = "UIN_DETAIL.ID";
    public static final String COL_STORE_ID = "UIN_DETAIL.STORE_ID";
    public static final String COL_STATUS = "UIN_DETAIL.STATUS";

    public static final int TYP_ID = Types.NUMERIC;
    public static final int TYP_STORE_ID = Types.NUMERIC;
    public static final int TYP_STATUS = Types.NUMERIC;

    public static final String SELECT_SQL = getSelectSqlText();
    public static final String INSERT_SQL = getInsertSqlText();
    public static final String UPDATE_SQL = getUpdateSqlText();
    public static final String DELETE_SQL = getDeleteSqlText();

    private Long id;
    private Long storeId;
    private Long status;

    public CustomUinDataBean() {
    }

    public String getSelectSql() {
        return SELECT_SQL;
    }

    public String getInsertSql() {
        return INSERT_SQL;
    }

    public String getUpdateSql() {
        return UPDATE_SQL;
    }

    public String getDeleteSql() {
        return DELETE_SQL;
    }
}

```

```

public Long getId() {
    return id;
}

public void setId(Long id) {
    this.id = id;
}

public void setId(long id) {
    this.id = id;
}

public Long getStoreId() {
    return storeId;
}

public void setStoreId(Long storeId) {
    this.storeId = storeId;
}

public void setStoreId(long storeId) {
    this.storeId = storeId;
}

public Long getStatus() {
    return status;
}

public void setStatus(Long status) {
    this.status = status;
}

public void setStatus(long status) {
    this.status = status;
}

public CustomUinDataBean read(ResultSet resultSet) throws SQLException {
    CustomUinDataBean bean = new CustomUinDataBean();
    bean.id = getLongFromResultSet(resultSet, "ID");
    bean.storeId = getLongFromResultSet(resultSet, "STORE_ID");
    bean.status = getLongFromResultSet(resultSet, "STATUS");
    return bean;
}

public List<Object> toList(boolean includePrimaryKey) {
    List<Object> list = new ArrayList<Object>();
    if (includePrimaryKey) {
        addToList(list, id, TYP_ID);
    }
    addToList(list, storeId, TYP_STORE_ID);
    addToList(list, status, TYP_STATUS);
    return list;
}
}

```

Example B-12 CustomUINEJBServices

```
package oracle.retail.sim.closed.custom;

import oracle.retail.sim.closed.common.BusinessException;
import oracle.retail.sim.closed.common.DowntimeException;
import oracle.retail.sim.closed.common.SimServerException;
import oracle.retail.sim.closed.ejb.CustomUINInterface;
import oracle.retail.sim.closed.logging.LogNames;
import oracle.retail.sim.closed.logging.LogService;
import oracle.retail.sim.closed.util.CompressedObject;
import oracle.retail.sim.closed.util.EJBServicesManager;
import oracle.retail.sim.closed.util.SimObjectUtils;
import oracle.retail.sim.closed.util.UniversalContext;

/**
 * Copyright 2004, 2011, Oracle. All rights reserved.
 */
public class CustomUINEJBServices extends CustomUINServices {
    private CustomUINInterface lookup() throws Exception {
        try {
            return (CustomUINInterface)
EJBServicesManager.cachedLookup("CustomUINBean");
        } catch (Throwable t) {
            throw new DowntimeException(
"An error occurred accessing CustomUINServices. Please contact your system
administrator.", t);
        }
    }

    private void removeCache() {
        EJBServicesManager.removeCache("CustomUINBean");
    }

    public void moveSerialNumbersToInStock(
java.util.List<oracle.retail.sim.closed.custom.CustomSerialNumber> arg0)
        throws Exception {
        Throwable causeOfException = null;
        int maxAttempts = EJBServicesManager.getMaxConnectAttempts();
        CompressedObject compressedSimSession =
            new CompressedObject(UniversalContext.getSession());
        CompressedObject compressed0 = new CompressedObject(arg0);
        if (LogService.isDebugEnabled(LogNames.SERIALIZED_OBJECT_SIZES)) {
            LogService.debug(LogNames.SERIALIZED_OBJECT_SIZES,
"CustomUINBean.moveSerialNumbersToInStock(compressed0, compressedSimSession)
(remote call) is sending " + SimObjectUtils.calculateByteSize(compressed0,
compressedSimSession) + " bytes in serialized object(s) for the remote call.");
        }
        for (int i = 0; i < maxAttempts; i++) {
            CustomUINInterface bean = lookup();
            try {
                long startTime = System.currentTimeMillis();
                CompressedObject compressedReturnVal =
                    bean.moveSerialNumbersToInStock(compressed0,
compressedSimSession);
                long endTime = System.currentTimeMillis();
                if (LogService.isDebugEnabled(LogNames.SERVICE_TIMINGS)) {
                    LogService.debug(LogNames.SERVICE_TIMINGS,
"CustomUINBean.moveSerialNumbersToInStock(compressed0, compressedSimSession)
(remote call) took " + (endTime - startTime) + "ms to complete");
                }
            }
        }
    }
}
```

```

    }
    if (LogService.isDebugEnabled(LogNames.SERIALIZED_OBJECT_SIZES)) {
        LogService.debug(LogNames.SERIALIZED_OBJECT_SIZES,
"CustomUINBean.moveSerialNumbersToInStock(compressed0, compressedSimSession)
(remote call) received " + SimObjectUtils.calculateByteSize(compressedReturnVal) +
" bytes in the returned serialized object.");
    }
    return;
} catch (SimServerException sse) {
    throw sse;
} catch (BusinessException be) {
    throw be;
} catch (Throwable t) {
    causeOfException = t;
    LogService.error(this, "Unexpected error in EJB connection
attempt: " + i, t);
    removeCache();
}
}
throw new DowntimeException("An error occurred accessing
CustomUINServices. Please contact your system administrator.", causeOfException);
}
}
}

```

Example B-13 CustomUINInterface

```

package oracle.retail.sim.closed.ejb;

import javax.ejb.Remote;
import oracle.retail.sim.closed.util.CompressedObject;

/**
 * Copyright 2004, 2011, Oracle. All rights reserved.
 */
@Remote
public interface CustomUINInterface {
    CompressedObject moveSerialNumbersToInStock(CompressedObject compressed0,
CompressedObject compressedSimSession) throws Exception;
}

```

Example B-14 CustomUINOracleDAO

```

package oracle.retail.sim.shared.dataaccess.dao;

import java.util.List;
import oracle.retail.sim.closed.common.SimServerException;
import oracle.retail.sim.closed.custom.CustomSerialNumber;
import oracle.retail.sim.closed.dataaccess.BaseOracleDao;
import oracle.retail.sim.closed.dataaccess.BatchParametricStatement;
import oracle.retail.sim.closed.uin.UINStatus;
import oracle.retail.sim.closed.util.CollectionUtil;
import oracle.retail.sim.shared.dataaccess.databean.generated.UinDetailDataBean;

/*****
*****
 * This class contains the database layer code for inserting new serial numbers
into
 * the database.
 * <p>

```

```

* This is future work-in-progress code for future SIM 14.0 or later release.
* <p>
* Copyright 2004, 2011, Oracle. All rights reserved.

*****
*****/
public class CustomUINOracleDao extends BaseOracleDao {

    public void saveSerialNumbers(Long storeId, List<CustomSerialNumber>
serialNumbers)
                                                    throws
SimServerException {
    StringBuilder sql = new StringBuilder();
    sql.append(" UPDATE ").append(UinDetailDataBean.TABLE_NAME);
    sql.append("     SET ").append(UinDetailDataBean.COL_STATUS).append(" = ?
");
    sql.append(" WHERE ").append(UinDetailDataBean.COL_ID).append(" = ? ");
    sql.append("     AND ").append(UinDetailDataBean.COL_STORE_ID).append(" = ?
");
    sql.append("     AND ").append(UinDetailDataBean.COL_STATUS).append(" = ?
");

    BatchParametricStatement batchStatement = new
BatchParametricStatement(sql.toString());
    List<Object> params = null;

    for (CustomSerialNumber serialNumber : serialNumbers) {
        params = CollectionUtil.newArrayList(2);
        params.add(UINStatus.IN_STOCK.getCode());
        params.add(serialNumber.getId());
        params.add(storeId);
        params.add(serialNumber.getStatus().getCode());

        batchStatement.addParams(params);
    }
    executeBatch(batchStatement);
}
}

```

Example B-15 CustomUINServerServices

```

package oracle.retail.sim.closed.custom;

import java.util.List;
import oracle.retail.sim.closed.util.UniversalContext;
import oracle.retail.sim.shared.dataaccess.dao.CustomUINOracleDao;

/**
 * Implements the Custom UIN services.
 * <p>
 * This is future work-in-progress code for future SIM 14.0 or later release.
 * <p>
 * Copyright 2004, 2011, Oracle. All rights reserved.
 */
public class CustomUINServerServices extends CustomUINServices {

    public void moveSerialNumbersToInStock(List<CustomSerialNumber> serialNumbers)
                                                    throws
Exception {
    CustomUINOracleDao dao = new CustomUINOracleDao();
}
}

```

```
        dao.saveSerialNumbers(UniversalContext.getStoreId(), serialNumbers);
    }
}
```

Example B-16 CustomUINServices

```
package oracle.retail.sim.closed.custom;

import java.util.List;

/**
 * Defines the API for Custom UIN Services.
 *
 * Copyright 2004, 2011, Oracle. All rights reserved.
 */
public abstract class CustomUINServices {
    /**
     * This API will move all serial numbers include in the parameters from the
     current status
     * to IN_STOCK. This will only happen if the serial number is currently in the
     status
     * specified in the parameter object. This will write a history record of the
     movement.
     * @param serialNumbers The serial numbers to update.
     */
    public abstract void moveSerialNumbersToInStock(List<CustomSerialNumber>
serialNumbers) throws Exception;
}
```