



Sun Cluster Data Service for N1 Grid Service Provisioning System for Solaris OS

Sun Microsystems, Inc.
4150 Network Circle
Santa Clara, CA 95054
U.S.A.

Part No: 817-5720
September 2004, Revision A

Copyright 2004 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. All rights reserved.

This product or document is protected by copyright and distributed under licenses restricting its use, copying, distribution, and decompilation. No part of this product or document may be reproduced in any form by any means without prior written authorization of Sun and its licensors, if any. Third-party software, including font technology, is copyrighted and licensed from Sun suppliers.

Parts of the product may be derived from Berkeley BSD systems, licensed from the University of California. UNIX is a registered trademark in the U.S. and other countries, exclusively licensed through X/Open Company, Ltd.

Sun, Sun Microsystems, the Sun logo, docs.sun.com, AnswerBook, AnswerBook2, and Solaris are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. in the U.S. and other countries. Products bearing SPARC trademarks are based upon an architecture developed by Sun Microsystems, Inc.

The OPEN LOOK and Sun™ Graphical User Interface was developed by Sun Microsystems, Inc. for its users and licensees. Sun acknowledges the pioneering efforts of Xerox in researching and developing the concept of visual or graphical user interfaces for the computer industry. Sun holds a non-exclusive license from Xerox to the Xerox Graphical User Interface, which license also covers Sun's licensees who implement OPEN LOOK GUIs and otherwise comply with Sun's written license agreements.

U.S. Government Rights – Commercial software. Government users are subject to the Sun Microsystems, Inc. standard license agreement and applicable provisions of the FAR and its supplements.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

Copyright 2004 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. Tous droits réservés.

Ce produit ou document est protégé par un copyright et distribué avec des licences qui en restreignent l'utilisation, la copie, la distribution, et la décompilation. Aucune partie de ce produit ou document ne peut être reproduite sous aucune forme, par quelque moyen que ce soit, sans l'autorisation préalable et écrite de Sun et de ses bailleurs de licence, s'il y en a. Le logiciel détenu par des tiers, et qui comprend la technologie relative aux polices de caractères, est protégé par un copyright et licencié par des fournisseurs de Sun.

Certaines parties de ce produit pourront être dérivées du système Berkeley BSD licenciés par l'Université de Californie. UNIX est une marque déposée aux États-Unis et dans d'autres pays et licenciée exclusivement par X/Open Company, Ltd.

Sun, Sun Microsystems, le logo Sun, docs.sun.com, AnswerBook, AnswerBook2, et Solaris sont des marques de fabrique ou des marques déposées de Sun Microsystems, Inc. aux États-Unis et dans d'autres pays. Toutes les marques SPARC sont utilisées sous licence et sont des marques de fabrique ou des marques déposées de SPARC International, Inc. aux États-Unis et dans d'autres pays. Les produits portant les marques SPARC sont basés sur une architecture développée par Sun Microsystems, Inc.

L'interface d'utilisation graphique OPEN LOOK et Sun™ a été développée par Sun Microsystems, Inc. pour ses utilisateurs et licenciés. Sun reconnaît les efforts de pionniers de Xerox pour la recherche et le développement du concept des interfaces d'utilisation visuelle ou graphique pour l'industrie de l'informatique. Sun détient une licence non exclusive de Xerox sur l'interface d'utilisation graphique Xerox, cette licence couvrant également les licenciés de Sun qui mettent en place l'interface d'utilisation graphique OPEN LOOK et qui en outre se conforment aux licences écrites de Sun.

CETTE PUBLICATION EST FOURNIE "EN L'ETAT" ET AUCUNE GARANTIE, EXPRESSE OU IMPLICITE, N'EST ACCORDEE, Y COMPRIS DES GARANTIES CONCERNANT LA VALEUR MARCHANDE, L'APTITUDE DE LA PUBLICATION A REpondre A UNE UTILISATION PARTICULIERE, OU LE FAIT QU'ELLE NE SOIT PAS CONTREFAISANTE DE PRODUIT DE TIERS. CE DENI DE GARANTIE NE S'APPLIQUERAIT PAS, DANS LA MESURE OU IL SERAIT TENU JURIDIQUEMENT NUL ET NON AVENU.



040812@9495



Contents

Installing and Configuring Sun Cluster HA for N1 Service Provisioning System	5
Accessing Sun Documentation Online	5
Ordering Sun Documentation	5
Typographic Conventions	5
Shell Prompts in Command Examples	6
Installing and Configuring Sun Cluster HA for N1 Service Provisioning System	6
Sun Cluster HA for N1 Service Provisioning System	8
Planning the Sun Cluster HA for N1 Service Provisioning System Installation and Configuration	8
Configuration Restrictions	9
Configuration Requirements	9
Installing and Configuring N1 Grid Service Provisioning System	13
▼ Installation of the N1 Grid Service Provisioning System components	13
Verifying the Installation and Configuration of N1 Grid Service Provisioning System	15
▼ How to Verify the Installation and Configuration of N1 Grid Service Provisioning System Master Server	15
▼ How to Verify the Installation and Configuration of N1 Grid Service Provisioning System Remote Agent	16
▼ How to Verify the Installation and Configuration of N1 Grid Service Provisioning System Local Distributor	17
Installing the Sun Cluster HA for N1 Grid Service Provisioning System Packages	18
▼ How to Install the Sun Cluster HA for N1 Service Provisioning System Packages Using the Web Start Program	18
▼ How to Install the Sun Cluster HA for N1 Service Provisioning System Packages Using the <code>scinstall</code> Utility	19
Preparation of the N1 Grid Service Provisioning System Master Servers database	20

▼ Preparation of the Master Servers database.	21
Registering and Configuring Sun Cluster HA for N1 Service Provisioning System	21
▼ How to Register and Configure Sun Cluster HA for N1 Service Provisioning System Master Server as a failover data service	21
▼ How to Register and Configure Sun Cluster HA for N1 Service Provisioning System Remote Agent as a failover data service	24
▼ How to Register and Configure Sun Cluster HA for N1 Service Provisioning System Local Distributor as a failover data service	25
Verifying the Sun Cluster HA for N1 Service Provisioning System and Configuration	27
▼ How to Verify the Sun Cluster HA for N1 Service Provisioning System Installation and Configuration	27
Understanding the Sun Cluster HA for N1 Service Provisioning System Master Server Parameter File	28
Structure of the Sun Cluster HA for N1 Service Provisioning System Master Servers parameter file	28
Strategy to Chose the TestCmd and the ReturnString Variable	29
Understanding the fault monitor of the Sun Cluster HA for N1 Service Provisioning System	30
Resource Properties	30
Probing Algorithm and Functionality for the N1 Grid Service Provisioning System Master Server	31
Probing Algorithm and Functionality for the N1 Grid Service Provisioning System Remote Agent	31
Probing Algorithm and Functionality for the N1 Grid Service Provisioning System Local Distributor	32
How to debug Sun Cluster HA for N1 Service Provisioning System	32
▼ How to turn debug on for a Sun Cluster HA for N1 Service Provisioning System component	33
Index	35

Installing and Configuring Sun Cluster HA for N1 Service Provisioning System

Accessing Sun Documentation Online

The docs.sun.comSM Web site enables you to access Sun technical documentation online. You can browse the docs.sun.com archive or search for a specific book title or subject. The URL is <http://docs.sun.com>.

Ordering Sun Documentation

Sun Microsystems offers select product documentation in print. For a list of documents and how to order them, see "Buy printed documentation" at <http://docs.sun.com>.

Typographic Conventions

The following table describes the typographic changes used in this book.

TABLE 1 Typographic Conventions

Typeface or Symbol	Meaning	Example
AaBbCc123	The names of commands, files, and directories; on-screen computer output	Edit your <code>.login</code> file. Use <code>ls -a</code> to list all files. <code>machine_name%</code> you have mail.
AaBbCc123	What you type, contrasted with on-screen computer output	<code>machine_name% su</code> Password:
<i>AaBbCc123</i>	Command-line placeholder: replace with a real name or value	To delete a file, type <code>rm filename</code> .
<i>AaBbCc123</i>	Book titles, new words, or terms, or words to be emphasized.	Read Chapter 6 in <i>User's Guide</i> . These are called <i>class</i> options. You must be <i>root</i> to do this.

Shell Prompts in Command Examples

The following table shows the default system prompt and superuser prompt for the C shell, Bourne shell, and Korn shell.

TABLE 2 Shell Prompts

Shell	Prompt
C shell prompt	<code>machine_name%</code>
C shell superuser prompt	<code>machine_name#</code>
Bourne shell and Korn shell prompt	<code>\$</code>
Bourne shell and Korn shell superuser prompt	<code>#</code>

Installing and Configuring Sun Cluster HA for N1 Service Provisioning System

Table 3 list the tasks for installing and configuring Sun Cluster HA for N1 Service Provisioning System. Perform these tasks in the order they are listed.

TABLE 3 Task Map: Installing and Configuring Sun Cluster HA for N1 Service Provisioning System

Task	For Instructions, Go To
1 Plan the installation.	"Planning the Sun Cluster HA for N1 Service Provisioning System Installation and Configuration" on page 8
2 Install and configure the N1 Grid Service Provisioning System.	"Installing and Configuring N1 Grid Service Provisioning System" on page 13
3 Verify installation and configuration.	"How to Verify the Installation and Configuration of N1 Grid Service Provisioning System Master Server" on page 15
4 Install Sun Cluster HA for N1 Service Provisioning System Packages.	"Installing the Sun Cluster HA for N1 Grid Service Provisioning System Packages" on page 18
5 Register and configure Sun Cluster HA for N1 Service Provisioning System components	"Registering and Configuring Sun Cluster HA for N1 Service Provisioning System" on page 21
5.1 Register and configure Sun Cluster HA for N1 Service Provisioning System Master Server as a failover data service.	"How to Register and Configure Sun Cluster HA for N1 Service Provisioning System Master Server as a failover data service" on page 21
5.2 Register and configure Sun Cluster HA for N1 Service Provisioning System Remote Agent as a failover data service.	"How to Register and Configure Sun Cluster HA for N1 Service Provisioning System Remote Agent as a failover data service" on page 24
5.3 Register and Configure Sun Cluster HA for N1 Service Provisioning System Local Distributor as a failover data service.	"How to Register and Configure Sun Cluster HA for N1 Service Provisioning System Local Distributor as a failover data service" on page 25
6 Verify Sun Cluster HA for N1 Service Provisioning System Installation and Configuration.	"How to Verify the Sun Cluster HA for N1 Service Provisioning System Installation and Configuration" on page 27
7 Understanding the Sun Cluster HA for N1 Service Provisioning System parameter file.	"Understanding the Sun Cluster HA for N1 Service Provisioning System Master Server Parameter File" on page 28
8 Understanding the Sun Cluster HA for N1 Service Provisioning System Fault Monitor.	"Understanding the fault monitor of the Sun Cluster HA for N1 Service Provisioning System" on page 30
9 How to debug Sun Cluster HA for N1 Service Provisioning System.	"How to turn debug on for a Sun Cluster HA for N1 Service Provisioning System component" on page 33

Sun Cluster HA for N1 Service Provisioning System

The N1 Grid Service Provisioning System is Sun Microsystems product for service (software) Distribution in the N1 environment. It consists of four components:

1. The Master Server which is the core component for the service distribution.
2. The client component is called Remote Agent. It has to run on every target host.
3. A proxy component called Local Distributor. The Local Distributor is used to minimize data transfer between datacenters.
4. A command line interface which can be installed on every host.

The Master Server is built upon Apache Tomcat and the PostgreSQL Database. All other components are pure Java.

The Sun Cluster HA for N1 Service Provisioning System data service provides mechanisms for orderly startup and shutdown, fault monitoring, and automatic failover of the Master Server, the Remote Agent and the Local Distributor.

The following table describes the relation between the application components and the related Sun Cluster data service.

TABLE 4 Protection of Components

Component	Protected by
Master Server	Sun Cluster HA for N1 Service Provisioning System
Remote Agent	Sun Cluster HA for N1 Service Provisioning System
Local Distributor	Sun Cluster HA for N1 Service Provisioning System

Planning the Sun Cluster HA for N1 Service Provisioning System Installation and Configuration

This section contains the information you need to plan your Sun Cluster HA for N1 Service Provisioning System installation and configuration.

Configuration Restrictions

This paragraph provides a list of software and hardware configuration restrictions that apply to Sun Cluster HA for N1 Service Provisioning System only.

For restrictions that apply to all data services, see the *Sun Cluster Release Notes*.

- **Sun Cluster HA for N1 Service Provisioning System can only be configured as a failover data service** — Each component of N1 Grid Service Provisioning System can operate as a failover data service only. Therefore, all the components of the Sun Cluster HA for N1 Service Provisioning System can only be configured to run as failover data services.
- **Install the N1 Grid Service Provisioning System components on shared storage** — The Master Server and the Local Distributor have to be installed on the shared storage. The remote agents which are configured to bind on the logical host have to be installed on the shared storage as well.
- **Configure a Sun Cluster resource for the N1 Grid Service Provisioning System Remote Agent for raw and ssl communication only** — The Master Server will start and stop the Remote Agent on every connection, as long as the Remote agent is configured for ssh communication. In this case, there is no Sun Cluster resource needed. In the ssh scenario, you have to install the N1 Grid Service Provisioning System Remote Agent on the shared storage and copy the ssh keys from one node to the remaining nodes of the cluster. This assures that all the cluster nodes have the same ssh personality.



Caution – Your data service configuration might not be supported if you do not adhere to these restrictions.

Configuration Requirements

These requirements apply to Sun Cluster HA for N1 Service Provisioning System only. You must meet these requirements before you proceed with your Sun Cluster HA for N1 Service Provisioning System installation and configuration.



Caution – Your data service configuration might not be supported if you do not adhere to these requirements.

- **Configure the N1 Grid Service Provisioning System base directory on shared storage on a failover file system** – Create the N1 Grid Service Provisioning System base directory on the shared storage. The location for the base directory can reside on a Global File System (GFS) or it can reside on a Failover File System (FFS) with an HAStoragePlus resource. It is best practice to store it on a FFS.

The FFS is required because the Master Server uses the directory structure to store its configuration, logs, deployed applications, database and so on. The Remote agent and the Local Distributor store their caches below the base directory. It is not recommended to store the binaries on the local storage and the dynamic parts of the data on the shared storage.

Note – It is best practice to mount Global File Systems with the /global prefix and to mount Failover File Systems with the /local prefix.

- **N1 Grid Service Provisioning System components and dependencies** – You can configure the Sun Cluster HA for N1 Service Provisioning System data service to protect one or more N1 Grid Service Provisioning System instances or components. Each instance or component needs to be covered by one Sun Cluster HA for N1 Service Provisioning System resource. The dependencies between the Sun Cluster HA for N1 Service Provisioning System resource and other necessary resources are described in [Table 5](#).

TABLE 5 Sun Cluster HA for N1 Service Provisioning System components and its dependencies for a failover configuration (via → symbol)

Component	Description
Storage Resource	This resource can be a <i>SUNW.HAStoragePlus</i> or a <i>SUNW.HAStorage</i> resource type.
N1 Grid Service Provisioning System component (Mandatory)	→ <i>SUNW.HAStoragePlus</i> / <i>SUNW.HAStorage</i> resource The Storage resource manages the N1 Grid Service Provisioning System File System mount points and ensures that N1 Grid Service Provisioning System component resource is not started until necessary file systems are mounted. The N1 Grid Service Provisioning System component resource can be the Master Server, the Remote Agent, or the Local Distributor.
Logical Host (Mandatory)	The N1 Grid Service Provisioning System has an implicit dependency on the logical hosts of the resource group, because it is based on the generic data service. Therefore, a logical host is required, but no explicit dependency is necessary.

Note – For more detailed information about N1 Grid Service Provisioning System, refer to the product documentation on the docs.sun.com webpage or the documentation delivered with the product.

Each component of Sun Cluster HA for N1 Service Provisioning System has configuration and registration files in the directory `/opt/SUNWscsps/component-dir/util` — The term `component-dir` stands for the directory names `master`, `localdist` or `remoteagent`. These files let you register the N1 Grid Service Provisioning System component with Sun Cluster.

Within these files, you apply the appropriate dependencies.

■

EXAMPLE 1 N1 Grid Service Provisioning System master components configuration and registration file for Sun Cluster

```
# cd /opt/SUNWscsps/master
#
# ls -l util
total 6
-rwxr-xr-x  1 root    other      730 Nov 26 10:49 db_prep_postgres
-rwxr-xr-x  1 root    other      674 Nov 26  09:44 spsma_config
-rwxr-xr-x  1 root    other      579 Nov 26 11:06 spsma_register
# more util/spsma_config
#
# Copyright 2003 Sun Microsystems, Inc. All rights reserved.
# Use is subject to license terms.
#
# This file will be sourced in by spsma_register and the parameters
# listed below will be used.
#
# These parameters can be customized in (key=value) form
#
#     RS - name of the resource for the application
#     RG - name of the resource group containing RS
#     PORT - name of the port number
#     LH - name of the LogicalHostname SC resource
#     PFILE - name of the parameter file for additional variables
#     HAS_RS - name of the HASStoragePlus SC resource
#
RS=
RG=
PORT=8080
LH=
PFILE=
HAS_RS=
```

The `spsma_register` script validates the variables of the `spsma_config` script and registers the resource for the master server.

The master server component has an additional script `db_prep_postgres`. The purpose of this script is to prepare the PostgreSQL database of the Master Server for monitoring.

■

EXAMPLE 2 N1 Grid Service Provisioning System Remote Agent components configuration and registration file for Sun Cluster

```
# cd /opt/SUNWscsps/remoteagent
#
# ls -l util
total 4
-rwxr-xr-x  1 root    other      777 Dec  2 12:48 spsra_config
-rwxr-xr-x  1 root    other      568 Jan  7 16:56 spsra_register
# more util/spsra_config
# Copyright 2003 Sun Microsystems, Inc. All rights reserved.
# Use is subject to license terms.
#
# This file will be sourced in by xxx_register and the parameters
# listed below will be used.
#
# These parameters can be customized in (key=value) form
#
#     RS - name of the resource for the application
#     RG - name of the resource group containing RS
#     PORT - name of the Remote Agents port number
#     LH - name of the LogicalHostname SC resource
#     USER - name of the owner of the remote agent
#     BASE - name of the directory where the N1 Service Provisioning Server
#           is installed
#     HAS_RS - name of the HAStoragePlus SC resource
#
#
RS=
RG=
PORT=22
LH=
USER=
BASE=
HAS_RS=
```

The `spsra_register` script validates the variables of the `spsra_config` script and registers the resource for the remote agent.



EXAMPLE 3 N1 Grid Service Provisioning System Local Distributors components configuration and registration file for Sun Cluster

```
# cd /opt/SUNWscsps/localdist
#
# ls -l util
total 4
-rwxr-xr-x  1 root    other      757 Dec  3 17:45 spsld_config
-rwxr-xr-x  1 root    other      609 Jan  7 16:56 spsld_register
# more util/spsld_config
#
# Copyright 2003 Sun Microsystems, Inc. All rights reserved.
# Use is subject to license terms.
#
```

EXAMPLE 3 N1 Grid Service Provisioning System Local Distributors components configuration and registration file for Sun Cluster *(Continued)*

```
# This file will be sourced in by spsld_register and the parameters
# listed below will be used.
#
# These parameters can be customized in (key=value) form
#
#       RS - name of the resource for the application
#       RG - name of the resource group containing RS
#       PORT - name of the port number
#       LH - name of the LogicalHostname SC resource
#       USER - name of the owner of the local distributor
#       BASE - name of the directory where the N1 Service Provisioning Server
#             is installed
#       HAS_RS - name of the HAStoragePlus SC resource
#
RS=
RG=
PORT=22
LH=
USER=
BASE=
HAS_RS=
```

The `spsld_register` script validates the variables of the `spsld_config` script and registers the resource for the local distributor.

Installing and Configuring N1 Grid Service Provisioning System

This section contains the procedures for installing and configuring N1 Grid Service Provisioning System components. The components are the Master Server, the Remote Agent and the Local Distributor.

▼ Installation of the N1 Grid Service Provisioning System components

1. **Determine how N1 Grid Service Provisioning System will be deployed in the Sun Cluster**
 - Determine which component of the N1 Grid Service Provisioning System you will use.

- Determine which user name will run N1 Grid Service Provisioning System component.
- Determine how many N1 Grid Service Provisioning System component versions and instances will be deployed.
- Determine which Cluster File System will be used by each N1 Grid Service Provisioning System component instance.

2. Mount the N1 Grid Service Provisioning Systems Cluster File Systems

3. Create user and group if required — If the N1 Grid Service Provisioning System is to run under a non root user, you have to create the appropriate user, and the appropriate group. For these tasks use the following commands on every node.

```
# groupadd -g 1000 sps
# useradd -u 1000 -g 1000 -d /global/sps -s /bin/ksh sps
```

Now you have to set up a resource group and the appropriate storage and logical host resources for the N1 Grid Service Provisioning System component. The component is either the Master Server, the Remote Agent, or the Local Distributor. These steps are required before proceeding with the N1 Grid Service Provisioning System resources. Perform the steps [Step 4](#) to [Step 9](#) on one node only

4. Register the SUNW.HAStoragePlus resource type.

It is assumed that the file system of the N1 Grid Service Provisioning System component will be mounted as a failover file system.

```
# scrgadm -a -t SUNW.HAStoragePlus
```

5. Create a failover resource group.

```
# scrgadm -a -g N1sps-component-resource-group
```

6. Create a resource for the N1 Grid Service Provisioning System component Disk Storage.

```
# scrgadm -a -j N1sps-component-has-resource \
> -g N1sps-component-resource-group \
> -t SUNW.HAStoragePlus \
> -x FilesystemMountPoints=N1sps-component-instance-mount-points
```

7. Create a resource for the N1 Grid Service Provisioning System Master component Logical Host name.

```
# scrgadm -a -L -j N1sps-component-logical-hostname \
> -g N1sps-component-resource-group \
> -l N1sps-component-logical-hostname
```

8. Enable the failover resource group, which now includes the N1 Grid Service Provisioning System Disk Storage and Logical Hostname resources.

```
# scswitch -z -g N1sps-component-resource-group
```

9. Install the N1 Grid Service Provisioning System components — Install the appropriate N1 Grid Service Provisioning System components on one node. Use

a shared file system within Sun Cluster for the installation location.

It is recommended that you install N1 Grid Service Provisioning System onto shared disks. For a discussion of the advantages and disadvantages of installing the software on a local versus a cluster file system, see “Determining the Location of the Application Binaries” in the *Sun Cluster Data Services Installation and Configuration Guide*.

Note – Refer to the N1 Grid Service Provisioning System product documentation on <http://docs.sun.com> for instructions about installing N1 Grid Service Provisioning System. For more information about N1 Grid Service Provisioning System, refer to the docs.sun.com web page.

Verifying the Installation and Configuration of N1 Grid Service Provisioning System

This section contains the procedure you need for verifying the installation and configuration of N1 Grid Service Provisioning System.

This procedure does not verify that your applications are highly available because you have not installed your data service yet. Select the appropriate procedure for the N1 Grid Service Provisioning System application you installed.

▼ How to Verify the Installation and Configuration of N1 Grid Service Provisioning System Master Server

This procedure is for the installation verification of the master server.

1. Start the N1 Grid Service Provisioning System Master Server.

Switch to the N1 Grid Service Provisioning System Master Servers user name (in the following example, it is `sps`) and change to the directory where the software is located. In the following example the software version is 4.1.

Note – The output messages of the start and shutdown commands are highly version dependent.

```
# su - sps
$ cd N1_Service_Provisioning_System_4.1
$cd server/bin
$./cr_server start
*** Starting database
*** Starting cr_server
```

2. Check the Installation

Start a web browser and connect to the cluster node with *http://logical-hostname:port*. The port is the web administration port configured in the installation procedure of the master server. If you see the default N1 Grid Service Provisioning System login page everything is working correctly.

3. Stop the N1 Grid Service Provisioning System Master Server.

```
$ ./cr_server stop
*** Stopping cr_server
Waiting for CR to complete shutdown...
*** Stopping database
waiting for postmaster to shut down.....done
postmaster successfully shut down
```

▼ How to Verify the Installation and Configuration of N1 Grid Service Provisioning System Remote Agent

This procedure is for the installation verification of the N1 Grid Service Provisioning System Remote Agent.

1. Start the N1 Grid Service Provisioning System Remote Agent.

Switch to the N1 Grid Service Provisioning System Remote Agents user name (in the following example, it is sps) and change to the directory where the software is located. In the following example the software version is 4.1.

Note – The output messages of the start and shutdown commands are highly version dependent.

```
# su - sps
$ cd N1_Service_Provisioning_System
$cd agent/bin
$./cr_agent start
```



```
*** Starting cr_agent
```

2. Check the Installation

Check the process table with the following command:

```
$ /usr/ucb/ps -auxww |grep java|grep agent >/dev/null;echo $?  
0
```

If the response is 0, everything is working correctly. You may omit the `|grep agent >/dev/null;echo $?` in this case you have to see a java process with agent in the process string.

3. Stop the N1 Grid Service Provisioning System Remote Agent.

```
$ ./cr_agent stop  
*** Stopping cr_agent
```

▼ How to Verify the Installation and Configuration of N1 Grid Service Provisioning System Local Distributor

This procedure is for the installation verification of the N1 Grid Service Provisioning System Local Distributor.

1. Start the N1 Grid Service Provisioning System Local Distributor.

Switch to the N1 Grid Service Provisioning System Remote Agents user name (in the following example, it is sps) and change to the directory the software is located. In the following example the software version is 4.1.

Note – The output messages of the start and shutdown commands are highly version dependent.

```
# su - sps  
$ cd N1_Service_Provisioning_System  
$cd ld/bin  
$./cr_ld start  
*** Starting cr_ld
```

2. Check the Installation

Check the process table with the following command:

```
$ /usr/ucb/ps -auxww |grep java|grep ld>/dev/null;echo $?  
0
```

If the response is 0, everything is working correctly. You may omit the `|grep ld>/dev/null;echo $?` in this case you have to see a java process with ld in the process string.

3. Stop the N1 Grid Service Provisioning System Local Distributor.

```
$ ./cr_ld stop
*** Stopping cr_ld
```

Installing the Sun Cluster HA for N1 Grid Service Provisioning System Packages

If you did not install the Sun Cluster HA for N1 Service Provisioning System packages during your initial Sun Cluster installation, perform this procedure to install the packages. Perform this procedure on each cluster node where you are installing the Sun Cluster HA for N1 Service Provisioning System packages. To complete this procedure, you need the Sun Java Enterprise System Accessory CD Volume 3.

If you are installing more than one data service simultaneously, perform the procedure in “Installing the Software” in *Sun Cluster 3.1 10/03 Software Installation Guide*.

Install the Sun Cluster HA for N1 Service Provisioning System packages by using one of the following installation tools:

- The Web Start program
- The `scinstall` utility

Note – The Web Start program is *not* available in releases earlier than Sun Cluster 3.1 Data Services 10/03.

▼ How to Install the Sun Cluster HA for N1 Service Provisioning System Packages Using the Web Start Program

You can run the Web Start program with a command-line interface (CLI) or with a graphical user interface (GUI). The content and sequence of instructions in the CLI and the GUI are similar. For more information about the Web Start program, see the `installer(1M)` man page.

1. **Become superuser on the cluster node where you are installing the Sun Cluster HA for N1 Service Provisioning System packages.**
2. **(Optional) If you intend to run the Web Start program with a GUI, ensure that your `DISPLAY` environment variable is set.**

3. Load the Sun Java Enterprise System Accessory CD Volume 3 into the CD-ROM drive.

If the Volume Management daemon `vold(1M)` is running and configured to manage CD-ROM devices, it automatically mounts the CD-ROM on the `/cdrom/cdrom0` directory.

4. Change to the Sun Cluster HA for N1 Service Provisioning System component directory of the CD-ROM.

The Web Start program for the Sun Cluster HA for N1 Service Provisioning System data service resides in this directory.

```
# cd /cdrom/cdrom0/components/SunCluster_HA_N1G_SPS_3.1
```

5. Start the Web Start program.

```
# ./installer
```

6. When you are prompted, select the type of installation.

- To install only the C locale, select Typical.
- To install other locales, select Custom.

7. Follow instructions on the screen to install the Sun Cluster HA for N1 Service Provisioning System packages on the node.

After the installation is finished, the Web Start program provides an installation summary. This summary enables you to view logs that the Web Start program created during the installation. These logs are located in the `/var/sadm/install/logs` directory.

8. Exit the Web Start program.

9. Unload the Sun Java Enterprise System Accessory CD Volume 3 from the CD-ROM drive.

- a. To ensure that the CD-ROM is not being used, change to a directory that does *not* reside on the CD-ROM.
- b. Eject the CD-ROM.

```
# eject cdrom
```

▼ How to Install the Sun Cluster HA for N1 Service Provisioning System Packages Using the `scinstall` Utility

You need the Sun Cluster Agents CD-ROM to perform this procedure. It is assumed that you did not install the data service during your initial Sun Cluster installation.

If you installed Sun Cluster HA for N1 Service Provisioning System as a part of your initial Sun Cluster installation, proceed to [“Registering and Configuring Sun Cluster HA for N1 Service Provisioning System”](#) on page 21.

Perform this procedure, on all nodes that can run Sun Cluster HA for N1 Service Provisioning System.

- 1. Load the Sun Cluster Agents CD-ROM into the CD-ROM drive.**
- 2. Run the `scinstall` utility with no options.**
The `scinstall` utility prompts you for additional information.
- 3. Chose the menu option, Add Support for New Data Service to this Cluster Node**
This step starts the `scinstall` utility in interactive mode.
- 4. Provide the pathname to the Sun Cluster Agents CD-ROM.**
The utility refers to the CD as “data services cd.”
- 5. Chose the menu option, q) done.**
- 6. Type yes for the question, Do you want to see more data services?**
The utility refers to the CD as “data services cd.”
- 7. Specify the data service to install.**
The `scinstall` utility lists the data service that you selected and asks you to confirm your choice.
- 8. Exit the `scinstall` utility.**
- 9. Unload the CD from the CD-ROM drive.**

Preparation of the N1 Grid Service Provisioning System Master Servers database

In this section you prepare the database of the N1 Grid Service Provisioning System Master Server. It needs to contain the user `sc_test` and the table `sc_test`. The user and the table are needed to monitor the PostgreSQL database. The script `db_prep_postgres` is provided to create the user and the table.

▼ Preparation of the Master Servers database.

1. **Start the N1 Grid Service Provisioning System Master Server as described in “How to Verify the Installation and Configuration of N1 Grid Service Provisioning System Master Server” on page 15.**

2. **Remain within the user of the Master Server and prepare the database.**

For the preparation of the database you need the N1 Grid Service Provisioning System Master Servers base directory. It is the directory that contains the server/bin directory. You prepare the database with the following command:

```
$/opt/SUNWscsps/master/util/db_prep_postgres <Base Directory of the master Server>  
CREATE USER  
CREATE
```

An example for the Base Directory

```
is:/global/sps/N1_Service_Provisioning_System_4.1.
```

3. **Stop the N1 Grid Service Provisioning System Master Server as described in “How to Verify the Installation and Configuration of N1 Grid Service Provisioning System Master Server” on page 15.**

Registering and Configuring Sun Cluster HA for N1 Service Provisioning System

This section contains the procedures you need to configure the Master Server, the Remote Agent, or the Local Distributor of Sun Cluster HA for N1 Service Provisioning System.

▼ How to Register and Configure Sun Cluster HA for N1 Service Provisioning System Master Server as a failover data service

This procedure assumes that you installed the data service packages.

If you did not install the Sun Cluster HA for N1 Service Provisioning System packages, go to “Installing the Sun Cluster HA for N1 Grid Service Provisioning System Packages” on page 18.

1. **Become superuser on one of the nodes in the cluster that will host N1 Grid Service Provisioning System Master Server.**
2. **Register the SUNW.gds resource type.**

```
# scrgadm -a -t SUNW.gds
```

3. Prepare the parameter file, which is required by the Sun Cluster HA for N1 Service Provisioning System Master Server.



Caution – The parameter files need to be available on every node that can host the N1 Grid Service Provisioning System Master Server data service. For a failover configuration store them on the shared storage. The parameter files cannot differ for a specific instance of N1 Grid Service Provisioning System Master Server on the various nodes.

```
# cd /opt/SUNWscsps/master/bin
# cp pfile desired place
```

Choose a location on the shared storage for the pfile. Edit the parameter file pfile and follow the comments within that file. For example:

```
#!/usr/bin/ksh
#
# Copyright 2003 Sun Microsystems, Inc. All rights reserved.
# Use is subject to license terms.
#
# Set theN1 Grid Service Provisioning System Master Server specific environment variables which
# and check fuctions will use
#
# User          Centerrun User
# Basepath      Absolute path to Centerrun Basedir directory
# Host          Hostname to test Apache Tomcat
# Tport        Port where the N1 Service Proisioning Systems Apache Tomcat instance
#              is configured to listen
# TestCmd      Apache Tomcat test command
# ReturnString Use one of the strings below faccording to your Sun One Provisoning
#              Server Version.
#              Version 4.1 = SSL|Service
# Startwait    Sleeping $Startwait seconds after completion of the
#              start command
User=
Basepath=
Host=
Tport=
TestCmd=""
ReturnString=
Startwait=
```

The following is an example for a N1 Grid Service Provisioning System 4.1 Master Server.

```
User=sps
Basepath=/global/sps/N1_Service_Provisioning_System_4.1
Host=N1spsma-lh
Tport=8080
TestCmd="get /index.jsp"
```

```
ReturnString="SSL|Service"  
Startwait=20
```

This example is from an N1 Grid Service Provisioning System 4.1 Master Server. The Apache Tomcat is configured to listen on Port 8080. The default start page contains the string *Service*, or the string *SSL* if you configured it to respond on the SSL Port.

4. Configure the registration scripts for each required N1 Grid Service Provisioning System Master Server instance.

```
# cd /opt/SUNWscsps/master/util  
# cp spsma_config desired place  
# cp spsma_register desired place
```

Edit the `spsma_config` file and follow the comments within that file. For example:

```
# These parameters can be customized in (key=value) form  
#  
# Copyright 2003 Sun Microsystems, Inc. All rights reserved.  
# Use is subject to license terms.  
#  
# This file will be sourced in by spsma_register and the parameters  
# listed below will be used.  
#  
# These parameters can be customized in (key=value) form  
#  
# RS - name of the resource for the application  
# RG - name of the resource group containing RS  
# PORT - name of the port number to satisfy GDS registration  
# LH - name of the LogicalHostname SC resource  
# PFILE - name of the parameter file for additional variables  
# HAS_RS - name of the HASToragePlus SC resource  
#  
RS=  
RG=  
PORT=  
LH=  
PFILE=  
HAS_RS=
```

The following is an example for the Sun Cluster HA for N1 Service Provisioning System Master Server.

```
RS=N1spsma-res  
RG=N1spsma-rg  
PORT=8080  
LH=N1spsma-lh  
PFILE=/global/mnt1/N1spsma-pfile  
HAS_RS=N1spsma-hastplus-res
```

The `PORT` variable is needed to satisfy the requirements of the generic data service.

5. After editing `spsma_config` register the resource.

```
# ./spsma_register  
Registration of resource N1spsma-rs succeeded
```

```
Validate resource N1spsma-rs in resourcegroup spsma-rg
Validation of resource spsma-rs succeeded
&#
```

6. Enable each N1 Grid Service Provisioning System Master Server resource.

```
# scstat -g
# scswitch -e -j N1spsma-resource
```

Repeat [Step 3](#) to [Step 6](#) for each N1 Grid Service Provisioning System Master Server instance you need.

▼ How to Register and Configure Sun Cluster HA for N1 Service Provisioning System Remote Agent as a failover data service

This procedure assumes that you installed the data service packages.

If you did not install the Sun Cluster HA for N1 Service Provisioning System packages, go to [“Installing the Sun Cluster HA for N1 Grid Service Provisioning System Packages”](#) on page 18.

1. Become superuser on one of the nodes in the cluster that will host N1 Grid Service Provisioning System Remote Agent.

2. Register the SUNW.gds resource type.

```
# scrgadm -a -t SUNW.gds
```

3. Configure the registration scripts for each required N1 Grid Service Provisioning System Remote Agents instance.

```
# cd /opt/SUNWscsps/remoteagent/util
# cp spsra_config desired place
# cp spsra_register desired place
```

Edit the `spsra_config` file and follow the comments within that file. For example:

```
#
# Copyright 2003 Sun Microsystems, Inc. All rights reserved.
# Use is subject to license terms.
#
# This file will be sourced in by spsra_register and the parameters
# listed below will be used.
#
# These parameters can be customized in (key=value) form
#
# RS - name of the resource for the application
# RG - name of the resource group containing RS
```



```

#      PORT - name of the port number to satisfy GDS registration
#      LH - name of the LogicalHostname SC resource
#      USER - name of the owner of the remote agent
#      BASE - name of the directory where the N1 Service Provisioning Server
#             is installed
#      HAS_RS - name of the HAStoragePlus SC resource
#

```

```

RS=
RG=
PORT=
LH=
USER=
BASE=
HAS_RS=

```

The following is an example for the N1 Grid Service Provisioning System 4.1 Remote Agent.

```

RS=N1spsra-res
RG=N1spsra-rg
PORT=22
LH=N1spsra-lh
USER=sps
BASE=/global/sps/N1_Service_Provisioning_System
HAS_RS=N1spsra-hastplus-res

```

The PORT variable is needed to satisfy the requirements of the generic data service.

4. After editing `spsra_config` register the resource.

```

# ./spsra_register
Registration of resource N1spsra-rs succeeded
Validate resource N1spsra-rs in resourcegroup N1spsra-rg
Validation of resource N1spsra-rs succeeded

```

5. Enable each N1 Grid Service Provisioning System Remote Agent resource.

```

# scstat -g

# scswitch -e -j N1spsra-resource

```

Repeat [Step 3](#) to [Step 6](#) for each N1 Grid Service Provisioning System Remote Agent instance you need.

▼ How to Register and Configure Sun Cluster HA for N1 Service Provisioning System Local Distributor as a failover data service

This procedure assumes that you installed the data service packages.

If you did not install the Sun Cluster HA for N1 Service Provisioning System packages, go to [“Installing the Sun Cluster HA for N1 Grid Service Provisioning System Packages”](#) on page 18.

1. Become superuser on one of the nodes in the cluster that will host N1 Grid Service Provisioning System Local Distributor.

2. Register the SUNW.gds resource type.

```
# scrgadm -a -t SUNW.gds
```

3. Configure the registration scripts for each required N1 Grid Service Provisioning System Local Distributor instance.

```
# cd /opt/SUNWscsps/localdist/util
# cp spsld_config desired place
# cp spsld_register desired place
```

Edit the `spsld_config` file and follow the comments within that file. For example:

```
#
# Copyright 2003 Sun Microsystems, Inc. All rights reserved.
# Use is subject to license terms.
#
# This file will be sourced in by spsld_register and the parameters
# listed below will be used.
#
# These parameters can be customized in (key=value) form
#
#     RS - name of the resource for the application
#     RG - name of the resource group containing RS
#     PORT - name of the port number to satisfy GDS registration
#     LH - name of the LogicalHostname SC resource
#     USER - name of the owner of the local distributor
#     BASE - name of the directory where the N1 Service Provisioning Server
#           is installed
#     HAS_RS - name of the HAStoragePlus SC resource
#
RS=
RG=
PORT=22
LH=
USER=
BASE=
HAS_RS=
```

The following is an example for N1 Grid Service Provisioning System 4.1 Local Distributor.

```
RS=N1spsld-res
RG=N1spsld-rg
PORT=22
LH=N1spsld-lh
USER=sps
BASE=/global/sps/N1_Service_Provisioning_System_4.1
HAS_RS=N1spsld-hastplus-res
```

The `PORT` variable is needed to satisfy the requirements of the generic data service.

4. After editing `spsld_config` register the resource.

```
# ./spsld_register
Registration of resource N1spsld-rs succeeded
Validate resource N1spsld-rs in resourcegroup N1spsld-rg
Validation of resource N1spsld-rs succeeded
```

5. Enable each N1 Grid Service Provisioning System Local Distributor resource.

```
# scstat -g
# scswitch -e -j N1spsra-resource
```

Repeat [Step 3](#) to [Step 5](#) for each N1 Grid Service Provisioning System Local Distributor instance you need.

Verifying the Sun Cluster HA for N1 Service Provisioning System and Configuration

This section contains the procedure you need to verify that you installed and configured your data service correctly.

▼ How to Verify the Sun Cluster HA for N1 Service Provisioning System Installation and Configuration

1. Become superuser on one of the nodes in the cluster which will host the N1 Grid Service Provisioning System component. A component can be the Master Server, the Remote Agent or the Local Distributor.

2. Ensure all the N1 Grid Service Provisioning System resources are online with the command `scstat`.

```
# scstat -g
```

For each N1 Grid Service Provisioning System resource which is not online, use the `scswitch` command as follows.

```
# scswitch -e -j N1sps-resource
```

3. Run the `scswitch` command to switch the N1 Grid Service Provisioning System resource group to another cluster node, such as `node2` with the command described below.

```
# scswitch -z -g N1sps-resource-group -h node2
```

Understanding the Sun Cluster HA for N1 Service Provisioning System Master Server Parameter File

Use the information to understand the contents of the Sun Cluster HA for N1 Service Provisioning System Master Server parameter file. This section describes the structure and the content of the Sun Cluster HA for N1 Service Provisioning System Master Server parameter file, as well as the strategy to choose some of its variables.

Structure of the Sun Cluster HA for N1 Service Provisioning System Master Servers parameter file

Sun Cluster HA for N1 Service Provisioning System for the master server uses a parameter file to pass parameters to the start, stop and probe command. This parameter file needs to be a valid Korn shell script which sets several variables. The structure of this file appears in Table 6. For examples of the parameter file refer to “[Registering and Configuring Sun Cluster HA for N1 Service Provisioning System](#)” on page 21.

TABLE 6 Structure of the Sun Cluster HA for N1 Service Provisioning System Master Servers parameter file

Variable	Explanation
User	The owner of the N1 Grid Service Provisioning System Master Server instance.
Basepath	Basepath is the absolute pathname to the directory where the N1 Grid Service Provisioning System/server/bin directory resides. It is the directory you specified at installation time.
Host	The Host variable is the Host to test the functionality of the Apache Tomcat component of the N1 Grid Service Provisioning System Master Server. The test is done via a connection to Host:Tport.
Tport	A Port where the N1 Grid Service Provisioning Systems Apache Tomcat component is serving. This Port is used together with the Host to test the functionality of the Apache Tomcat server process of the N1 Grid Service Provisioning System Master Server.

TABLE 6 Structure of the Sun Cluster HA for N1 Service Provisioning System Master Servers parameter file (Continued)

Variable	Explanation
TestCmd	This variable represents the command which is passed to the N1 Grid Service Provisioning Systems Apache Tomcat server process to do a sanity check.
ReturnString	The variable ReturnString represents the string which must be present in the answer to the TestCmd. It can not be "Connection refused" because this string is in the answer when the N1 Grid Service Provisioning Systems Apache Tomcat server process is not running.
Startwait	This variable stands for the number of seconds to wait after the N1 Grid Service Provisioning System Master Server start command is completed. It lasts until the Apache Tomcat server process of the N1 Grid Service Provisioning System Master Server is fully operational. The absolute number of seconds depends on the speed and the load of the Hardware. A good strategy is to start with 60 seconds.

The parameters in [Table 6](#) can be changed at any time. The only difference is when changes take effect.

The following parameters of the Sun Cluster HA for N1 Service Provisioning System parameter file are used for starting and stopping the Master Server. Changes to these parameters take effect at every restart or disabling and enabling of a N1 Grid Service Provisioning System Master Server resource.

- User
- Basepath
- Startwait

The following parameters of the Sun Cluster HA for N1 Service Provisioning System Master Server parameter file are used within the fault monitor. Changes to these parameters take effect at every `Thorough_probe_interval`.

- Host
- Tport
- TestCmd
- ReturnString

Strategy to Chose the TestCmd and the ReturnString Variable

The ReturnString has to be present on the page you query with the test command TestCmd.

- Take the start page of your application and set the `TestCmd` to `get /index.jsp`. Set the `ReturnString` to a string contained in the startpage. With this strategy, you are monitoring that the Apache Tomcat process of the N1 Grid Service Provisioning System Master Server is operational.
- If the N1 Grid Service Provisioning System Master Server is configured for SSL on the administrative port. The only request on the http port is a page containing the string `SSL`. In this case configure the `ReturnString` to `SSL` and the `TestCmd` to `get /index.jsp`.
- If you expect changes in the configurations, configure the test command to `get /index.jsp` and the `ReturnString` to `SSL | Service`. This expression is true if the startpage contains `SSL` or `Service`.
- If none of the above is appropriate, set the `TestCmd` to `get /a-page-which-does-not-exists`. In this case, set the `ReturnString` to a string contained in the Error Page. With this strategy, you are monitoring that the Apache Tomcat process of the N1 Grid Service Provisioning System Master Server is operational, because it registers that it must deliver a page that does not exist.

You can evaluate the different pages by connecting using a browser with `hostname:port` and specifying the different pages.

Understanding the fault monitor of the Sun Cluster HA for N1 Service Provisioning System

This section describes the Sun Cluster HA for N1 Service Provisioning System fault monitor's probing algorithm and functionality, states the conditions, messages, recovery actions, and states the conditions and messages associated with unsuccessful probing.

For conceptual information on fault monitors, see the *Sun Cluster Concepts Guide*.

Resource Properties

The Sun Cluster HA for N1 Service Provisioning System fault monitor uses the same resource properties as the resource type `SUNW.gds`. Refer to the `SUNW.gds(5)` man page for a complete list of resource properties used.

Probing Algorithm and Functionality for the N1 Grid Service Provisioning System Master Server

The probing of the Master Server consists of two parts. One to probe the Apache Tomcat and a second part to probe the database.

The following steps are executed to monitor the sanity of the N1 Grid Service Provisioning System Master Server.

1. Sleeps for *Thorough_probe_interval*.
2. Pings the *Host*, which is configured in the Sun Cluster HA for N1 Service Provisioning System Master Server parameter file.
3. Connects to the Apache Tomcat via *Host* and *Port*. If the connection is successful it sends the *TestCmd* and tests whether the *ReturnString* comes back. If it fails, it is rescheduled after 5 seconds. If this fails again, then the probe will restart the Sun Cluster HA for N1 Service Provisioning System.



Caution – The *ReturnString* cannot be **Connection refused** because this string will be returned if no connection is possible.

4. If the Apache Tomcat is operational, the probe manipulates the database table *sc_test*. If the connection to the database or the table manipulation is unsuccessful, the N1 Grid Service Provisioning System Master server will be restarted.
5. If the Apache Tomcat process and all the database processes died, *pmf* will interrupt the probe to immediately restart the N1 Grid Service Provisioning System Master Server.
6. If the N1 Grid Service Provisioning System Master Server is repeatedly restarted and subsequently exhausts the *Retry_count* within the *Retry_interval*, then a failover is initiated for the resource group onto another node. This is done if the resource property *Failover_enabled* is set to `TRUE`.

Probing Algorithm and Functionality for the N1 Grid Service Provisioning System Remote Agent

The probing of the Remote Agent is done by *pmf* only.

The following steps are executed to monitor the N1 Grid Service Provisioning System Remote Agent.

1. If the process of the Remote Agent has died, *pmf* will immediately restart the N1 Grid Service Provisioning System Remote Agent.
2. If the N1 Grid Service Provisioning System Remote Agent is repeatedly restarted and subsequently exhausts the *Retry_count* within the *Retry_interval*, then a failover is initiated for the resource group onto another node. This is done if the

resource property `Failover_enabled` is set to `TRUE`.

Probing Algorithm and Functionality for the N1 Grid Service Provisioning System Local Distributor

The probing of the Local Distributor is done by `pmf` only.

The following steps are executed to monitor the N1 Grid Service Provisioning System Local Distributor.

1. If the process of the Local Distributor has died, `pmf` will immediately restart the N1 Grid Service Provisioning System Local Distributor.
2. If the N1 Grid Service Provisioning System Local Distributor is repeatedly restarted and subsequently exhausts the `Retry_count` within the `Retry_interval`, then a failover is initiated for the resource group onto another node. This is done if the resource property `Failover_enabled` is set to `TRUE`.

How to debug Sun Cluster HA for N1 Service Provisioning System

Sun Cluster HA for N1 Service Provisioning System can be used by multiple N1 Grid Service Provisioning System instances. However, it is possible to turn debug on for all N1 Grid Service Provisioning System instances or a particular N1 Grid Service Provisioning System instance. This has to be done for each component (Master Server, Remote Agent, or Local Distributor) on its own.

The Sun Cluster HA for N1 Service Provisioning System component has a `DEBUG` file under `/opt/SUNWscsps/component-dir/etc`. The directories of these components are `master` for the Master Server, `remoteagent` for the Remote Agent, and `localdist` for the Local Distributor.

This file allows you to switch debug on for all instances of a N1 Grid Service Provisioning System component, or for a specific instance of a N1 Grid Service Provisioning System component on a particular node in a Sun Cluster. If you require debug to be switched on for Sun Cluster HA for N1 Service Provisioning System across the whole Sun Cluster, you will need to repeat this step on all nodes within Sun Cluster.

▼ How to turn debug on for a Sun Cluster HA for N1 Service Provisioning System component

Perform these steps for the Sun Cluster HA for N1 Service Provisioning System component that requires debug output, on each node of Sun Cluster as required.

1. Edit `/etc/syslog.conf` and change `daemon.notice` to `daemon.debug`.

```
# grep daemon /etc/syslog.conf
*.err;kern.debug;daemon.notice;mail.crit      /var/adm/messages
*.alert;kern.err;daemon.err                  operator
#
```

Change the `daemon.notice` to `daemon.debug` and restart `syslogd`. Note that the output below, from the command `grep daemon /etc/syslog.conf`, shows that `daemon.debug` has now been set.

```
# grep daemon /etc/syslog.conf
*.err;kern.debug;daemon.debug;mail.crit      /var/adm/messages
*.alert;kern.err;daemon.err                  operator
#
# pkill -1 syslogd
```

2. Edit `/opt/SUNWscsps/component-dir/etc/config` and change `DEBUG=` to `DEBUG=ALL` or `DEBUG=resource`

```
# cat /opt/SUNWscsps/component-dir/etc/config
#
# Copyright 2003 Sun Microsystems, Inc. All rights reserved.
# Use is subject to license terms.
#
# Usage:
#     DEBUG=<RESOURCE_NAME> or ALL
#
DEBUG=ALL
#
```

Possible values for the `component-dir` are `master` for the Master Server, `remoteagent` for the Remote Agent, and `localdist` for the Local Distributor.

Note – To turn off debug, reverse the steps above.

Index

C

C locale, 19
commands
 cr_agent, 16, 17
 cr_ld, 17, 18
 cr_server, 16
 scinstall, 20
 scrgadm, 21, 24, 26
 scstat, 24, 25, 27
 scswitch, 14, 24, 25, 27
components, failover configuration, 10

D

database preparation, 21
dependencies, 10

E

enable Local Distributor resource, 27
enable Master Server resource, 24
enable Remote Agent resource, 25
enable resource group, 14

F

fault monitor, 30-32
files, installation logs, 19

I

install, 19-20
installing
 Sun Cluster HA for N1 Service Provisioning
 System
 by using Web Start program, 18-19
 log files created, 19

L

locales, 19
log files, installation, 19

P

parameter file, 22, 28-29
protection of components, 8

R

register, 23, 24, 26
registration files, 11
 spsld_config, 12-13, 26
 spsma_config, 11, 23
 spsra_config, 12, 24
registration scripts, 11, 12
requirements, 9-13
restrictions, 9

S

strategy, 29

V

/var/sadm/install/logs directory, 19

verify, 15-16, 16-17, 17-18, 27

W

Web Start program, 18-19