



Sun Management Center 3.6 Installation and Configuration Guide

Sun Microsystems, Inc.
4150 Network Circle
Santa Clara, CA 95054
U.S.A.

Part No: 817-7958-05
December 2005

Copyright 2005 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. All rights reserved.

This product or document is protected by copyright and distributed under licenses restricting its use, copying, distribution, and decompilation. No part of this product or document may be reproduced in any form by any means without prior written authorization of Sun and its licensors, if any. Third-party software, including font technology, is copyrighted and licensed from Sun suppliers.

Parts of the product may be derived from Berkeley BSD systems, licensed from the University of California. UNIX is a registered trademark in the U.S. and other countries, exclusively licensed through X/Open Company, Ltd.

Sun, Sun Microsystems, the Sun logo, docs.sun.com, AnswerBook, AnswerBook2, Java, Netra, Sun Fire, Sun StorEdge, Sun Enterprise, Ultra, Solstice SyMON, N1, Sun Blade, Sun N1 System Manager and Solaris are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. in the U.S. and other countries. Products bearing SPARC trademarks are based upon an architecture developed by Sun Microsystems, Inc. Netscape Navigator and Mozilla are trademarks or registered trademarks of Netscape Communications Corporation in the United States and other countries.

The OPEN LOOK and Sun™ Graphical User Interface was developed by Sun Microsystems, Inc. for its users and licensees. Sun acknowledges the pioneering efforts of Xerox in researching and developing the concept of visual or graphical user interfaces for the computer industry. Sun holds a non-exclusive license from Xerox to the Xerox Graphical User Interface, which license also covers Sun's licensees who implement OPEN LOOK GUIs and otherwise comply with Sun's written license agreements.

U.S. Government Rights – Commercial software. Government users are subject to the Sun Microsystems, Inc. standard license agreement and applicable provisions of the FAR and its supplements.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

Copyright 2005 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. Tous droits réservés.

Ce produit ou document est protégé par un copyright et distribué avec des licences qui en restreignent l'utilisation, la copie, la distribution, et la décompilation. Aucune partie de ce produit ou document ne peut être reproduite sous aucune forme, par quelque moyen que ce soit, sans l'autorisation préalable et écrite de Sun et de ses bailleurs de licence, s'il y en a. Le logiciel détenu par des tiers, et qui comprend la technologie relative aux polices de caractères, est protégé par un copyright et licencié par des fournisseurs de Sun.

Des parties de ce produit pourront être dérivées du système Berkeley BSD licenciés par l'Université de Californie. UNIX est une marque déposée aux Etats-Unis et dans d'autres pays et licenciée exclusivement par X/Open Company, Ltd.

Sun, Sun Microsystems, le logo Sun, docs.sun.com, AnswerBook, AnswerBook2, Java, Sun Fire, Sun StorEdge, Sun Enterprise, Ultra, Solstice SyMON, N1, Sun Blade, Sun N1 System Manager et Solaris sont des marques de fabrique ou des marques déposées, de Sun Microsystems, Inc. aux Etats-Unis et dans d'autres pays. Toutes les marques SPARC sont utilisées sous licence et sont des marques de fabrique ou des marques déposées de SPARC International, Inc. aux Etats-Unis et dans d'autres pays. Les produits portant les marques SPARC sont basés sur une architecture développée par Sun Microsystems, Inc. Netscape Navigator et Mozilla sont les marques de Netscape Communications Corporation aux Etats-Unis et dans d'autres pays.

L'interface d'utilisation graphique OPEN LOOK et Sun™ a été développée par Sun Microsystems, Inc. pour ses utilisateurs et licenciés. Sun reconnaît les efforts de pionniers de Xerox pour la recherche et le développement du concept des interfaces d'utilisation visuelle ou graphique pour l'industrie de l'informatique. Sun détient une licence non exclusive de Xerox sur l'interface d'utilisation graphique Xerox, cette licence couvrant également les licenciés de Sun qui mettent en place l'interface d'utilisation graphique OPEN LOOK et qui en outre se conforment aux licences écrites de Sun.

CETTE PUBLICATION EST FOURNIE "EN L'ETAT" ET AUCUNE GARANTIE, EXPRESSE OU IMPLICITE, N'EST ACCORDEE, Y COMPRIS DES GARANTIES CONCERNANT LA VALEUR MARCHANDE, L'APTITUDE DE LA PUBLICATION A REpondre A UNE UTILISATION PARTICULIERE, OU LE FAIT QU'ELLE NE SOIT PAS CONTREFAISANTE DE PRODUIT DE TIERS. CE DENI DE GARANTIE NE S'APPLIQUERAIT PAS, DANS LA MESURE OU IL SERAIT TENU JURIDIQUEMENT NUL ET NON AVENU.



051017@13215



Contents

Preface	15
1 Installing Sun Management Center 3.6	21
Installing the Product	21
Preinstallation Information	22
Sun Management Center Requirements	25
Installing the Required JDK Version	27
▼ To Install the Required JDK Version	27
Sun Management Center Base Add-on Requirements	27
Installing Sun Management Center	29
▼ To Install Sun Management Center	29
Setting Up Sun Management Center	33
▼ To Set Up Sun Management Center	33
(On Solaris 10) Monitoring a Zone Using Sun Management Center	40
▼ To Create a Local Zone	40
▼ To Use an Existing Local Zone	41
▼ To Monitor a Zone Using Sun Management Center	42
Supported Commands, Modules, and Add-ons	42
Sun Management Center Documentation Resources	43
2 Installation Overview	47
Sun Management Center Overview	47
Sun Management Center Architecture and Base Components	48
Sun Management Center Base Add-on Products	49
Additional Add-on Products	50
Developer Environment	50

Sun Management Center Directories	51
Sun Management Center System Files	51
Supported Platforms	53
Sample Sun Management Center Fresh Installation	55
▼ To Install Sun Management Center and ASM	56
Sun Management Center 3.0 to Sun Management Center 3.5 Update 2	58
▼ To Upgrade Sun Management Center 3.0 to Sun Management Center 3.5 Update 2	58
Sun Management Center 2.1.1 to Sun Management Center 3.5 Update 2 Upgrade	60
▼ To Upgrade From Sun Management Center 2.1.1 to Sun Management Center 3.5 Update 2	61
Using Agent-Update to Upgrade Agents to Sun Management Center 3.6	63
▼ To Upgrade Agents to Sun Management Center 3.6 Using Agent-Update	63
To Install the Sun Management Center Console on Microsoft Windows	64
Product Documentation	64
3 Configuration Considerations	65
Security Recommendations	65
Users, Groups, and Roles Overview	65
Sun Management Center Internal Security	67
Security Keys and SNMP Community String	68
Management Strategies	69
Server Contexts	69
Domain Strategies	69
Organization Strategies	70
Managing Large Enterprises	72
4 Preparing Systems for Sun Management Center Upgrade and Installation	73
Compatibility With Other Software and Earlier Versions of the Product	73
Preinstallation Checklist	74
Prerequisite Packages	76
Solaris Systems With More Than 4 Gbytes RAM	76
Java Environment Variables and Path	77
▼ To Set JAVA_HOME and PATH on the Solaris Platform	77
▼ To Set PATH on Microsoft Windows 98	77
▼ To Set PATH on Microsoft Windows NT or Microsoft Windows 2000	78
▼ To Set PATH on Linux	79

Microsoft Windows 98 Swap Space and Environment Space	79
▼ To Set Microsoft Windows 98 Minimum Swap Space Size	80
▼ To Set Microsoft Windows 98 Minimum Environment Space Size	81
Sun StorEdge A5x00 Packages	81
T3 Storage Devices	81
Preparing a T3 Storage Device	82
▼ To Prepare a T3 Storage Device	82
Removing T3 Device Configuration If Present	83
▼ To Remove T3 Device Configuration	84
Determining the Installation Source	85
Creating Installation CD Images	85
▼ To Create CD Images	85
Creating CD Images From the Download Tar File	87
▼ To Download the Tar File From the Web Site	88
5 Upgrading Previous Versions of SyMON and Sun Management Center on the Solaris Platform	91
Upgrade Considerations	91
Upgrading from Solstice SyMON 1.x and Sun Enterprise SyMON 2.x Software	92
Upgrading From Sun Management Center 2.1 or 2.1.1	93
▼ To Upgrade From a Sun Management Center 2.x Server	93
Upgrading From Sun Management Center 3.0	95
Upgrading the Server	95
▼ To Upgrade From Sun Management Center 3.0	95
Upgrade from 3.5 to 3.5 Update 1 or Update 2	97
Upgrade from 3.5 Update 1 or Update 2 to 3.6	98
Upgrading Agents	98
6 Installing and Updating Agents and Installing on Microsoft Windows	101
Creating Agent Installation and Update Images	101
▼ To Create an Agent-Update Image Using <code>es-gui-imagetool</code>	103
▼ To Create an Agent-Update Image Using <code>es-imagetool</code>	108
▼ To Create a Patch-Only Image Using the Image Tools	113
▼ To Create an Agent-Only Installation Image Using <code>es-makeagent</code>	119
Applying Agent Installation, Update, and Patch-Only Images	121
▼ To Install Agents From an Agent-Update Image Using the Manage Jobs Task	121

▼ To Install or Update Agents From an Agent-Update Image Using <code>agent-update.bin</code>	122
▼ To Install Agents From an Agent-Only Installation Image Using <code>es-inst -a</code>	124
Installing Agents Using JumpStart	126
JumpStart Concepts	126
JumpStart Configuration and Use	130
▼ To Create the JumpStart Install Server and Profile Directory	131
▼ To Create the Base Agent Image on the JumpStart Install Server	132
▼ To Generate the Sun Management Center 3.6 Install and Setup Response Files	133
▼ To Create the JumpStart Profiles	140
▼ To Create the JumpStart Finish Script	141
▼ To Create the JumpStart Rules File	144
▼ To Validate Your JumpStart Files	145
▼ To Add Install Client Information to the JumpStart Server	146
Configuring Server and Agent on Multi-IP Machines	148
Server Configuration	148
▼ To Add an IP Interface to the Sun Management Center Server	149
▼ To Remove an IP Interface From the Sun Management Center Server	150
Agent Configuration	150
▼ To Configure the Sun Management Center Agent on a Multi-IP Machine	151
Installing Sun Management Center 3.6 on Microsoft Windows	153
▼ To Install Sun Management Center 3.6 on Microsoft Windows	153
7 Sun Management Center Post-Installation Tasks	157
Setting Up Users	157
▼ To Add Sun Management Center Users	158
▼ To Assign a User to a Security Group	158
Stopping and Disabling the SNMP Daemons	159
▼ To Stop and Disable <code>snmpdx</code> Manually	160
▼ To Stop and Disable <code>SMA</code> Manually	160
Installing Separately Released Add-on Products	160
▼ To Set Up an Add-on Product Using <code>es-guisetup</code>	161
▼ To Set Up an Add-on Product Using <code>es-setup</code>	162
Sun Management Center Validation Tool	162
<code>es-validate</code> Options	163

8	Starting and Stopping Sun Management Center	165
	Commands Supported by the Linux Agent	165
	Starting Components on the Solaris Platform	166
	Starting Components Using <code>es-guistart</code>	166
	▼ To Start Sun Management Center Using <code>es-guistart</code>	166
	Starting Components Using <code>es-start</code>	167
	Starting the Console	168
	▼ To Start the Console on the Solaris Platform	168
	▼ To Start the Console on Microsoft Windows	169
	Stopping Components on the Solaris Platform	169
	Stopping Components Using <code>es-guistop</code>	170
	▼ To Stop Sun Management Center Components Using <code>es-guistop</code>	170
	Stopping Components Using <code>es-stop</code>	170
9	Sun Management Center Administration	173
	Sun Management Center Backup and Recovery	173
	Using <code>es-backup</code>	174
	▼ To Manually Back Up Sun Management Center Data to the Default Directory	175
	Using <code>es-restore</code>	177
	▼ To Restore Sun Management Center Data Using the Default Backup Directory	177
	Regenerating Security Keys	178
	▼ To Regenerate the Security Keys	179
	SNMP Daemons and Legacy Agents	180
	SNMP Overview	180
	Configuring a Legacy SNMP Agent as a Subagent of an Agent	181
	▼ To Configure a Legacy SNMP Agent as a Subagent of an Agent	181
	Reconfiguring Port Addresses	183
	Default Ports	183
	▼ To Determine Whether a Port Is Used	184
	Reconfiguring Sun Management Center Ports	185
	▼ To Reconfigure the Agent SNMP Port	185
	▼ To Reconfigure the Server RMI Port Address	185
	Using <code>es-config</code>	186
	Multiple Trap Destinations	189
	Using the <code>es-trapdest</code> Command	189
	Registration Trap Configuration	191

Assigning an Agent to a Different Server	192
▼ To Assign an Agent to a Different Server	193
Using Sun Management Center With a Firewall	196
▼ To Restrict the Firewall Port Range	196
Enabling Network Address Translation Support	197
▼ To Enable NAT Support	197
10 Integration With Other Enterprise Management Platforms	199
HP OpenView Operations Integration	199
HPOV Integration Key Features	199
HPOV Integration Key Components	200
HPOV Integration Prerequisites	200
HPOV Integration Supported Platforms	200
HPOV Integration Additional Documentation	200
BMC Patrol Integration	201
Computer Associates Unicenter TNG Integration	201
Unicenter TNG Integration Key Features	201
Unicenter TNG Integration Key Components	201
Unicenter TNG Integration Prerequisites	202
Unicenter TNG Integration Supported Platforms	202
Starting the Adaptor in Command—Line Interface	202
Starting the Adapter in Graphical User Interface	203
Unicenter TNG Integration Additional Documentation	203
Tivoli TME Integration	203
Tivoli TEC Integration Key Features	204
Tivoli TEC Integration Key Components	204
Tivoli TEC Integration Prerequisites	204
Tivoli TEC Supported Platforms	204
Additional Documentation	204
A Uninstalling SyMON and Sun Management Center	205
Uninstalling SyMON and Sun Management Center from the Solaris Platform	205
Uninstalling Solstice SyMON 1.x or Enterprise SyMON 2.x	206
▼ To Uninstall Solstice SyMON 1.x or Enterprise SyMON 2.x	206
Uninstalling Sun Management Center 2.x	206
▼ To Uninstall Sun Management Center 2.x	206
Uninstalling Sun Management Center 3.0	207

▼ To Uninstall Sun Management Center 3.0	207
Uninstalling Sun Management Center 3.6	209
▼ To Uninstall Sun Management Center 3.6 Using <code>es-guiuninst</code>	209
Uninstalling Sun Management Center From the Microsoft Windows Platform	211
▼ To Uninstall Sun Management Center From Microsoft Windows	211
B Using the Command Line for Uninstall, Install, and Setup	213
Uninstalling Sun Management Center	213
<code>es-uninst</code> Options	213
Uninstalling Sun Management Center Versions 2.x and 3.x	214
▼ To Uninstall Sun Management Center 2.x and 3.x Using <code>es-uninst</code>	215
Installing Sun Management Center Using <code>es-inst</code>	217
<code>es-inst</code> Options	217
Installing on a Local Machine	218
▼ To Install Using the <code>es-inst</code> Script	218
Installing on a Remote Machine	224
▼ To Install Patches for <code>pkgadd</code>	225
▼ To Prepare the Remote Machine	226
▼ To Install Sun Management Center on the Remote Machine	227
Setting Up Sun Management Center Using <code>es-setup</code>	229
When to Run Setup	229
<code>es-setup</code> Options	229
Setting Up Sun Management Center 3.6 Using <code>es-setup</code>	230
▼ To Set Up Sun Management Center Using the <code>es-setup</code> Script	231
C Determining Hardware Resources	239
Agent Layer Resources	239
x86 Agent Limitations	240
CPU Resources	240
Virtual Memory Requirements	242
Hardware-Specific Module Availability	242
Management Module Resources	243
Server Layer Resources	245
Recommended Server Hardware Platforms	245
Sizing Requirements	246
Sun Management Center Server with the Performance Reporting Manager Add-on	247
Performance Considerations	250

Java Console Layer Resources	252
Sun Fire Proxy/Platform Agent Resources	252
System Requirements	253
Startup of Multiple Platform Agents	254
D Network Address Translation	257
NAT Concepts	257
Use of IP Addresses With NAT	258
How NAT Works	258
Complexity of the NAT Solution	259
NAT Configuration	260
NAT Solution	261
NAT Limitations	261
NAT Examples	262
Single NAT Environment	262
Dual NAT Environment	263
E Sun Management Center 3.6 Packages	265
Index	275

Tables

TABLE 1-1	Information Needed Before Installing	23
TABLE 1-2	Information Needed Before Setting Up	24
TABLE 1-3	Sun Management Center 3.6 System Requirements	25
TABLE 1-4	Add-on Disk Space Requirements by Base Component	28
TABLE 1-5	Documentation Resources	43
TABLE 2-1	Sun Management Center Default Solaris Directories	51
TABLE 2-2	Examples of Supported Platforms	54
TABLE 4-1	Sun Management Center Prior Version Compatibility by Base Product	74
TABLE 6-1	System Services Required for the JumpStart Software	128
TABLE 6-2	esmultiip options	148
TABLE 7-1	es-validate Options	163
TABLE 8-1	es-start Options	167
TABLE 8-2	es-stop Options	171
TABLE 9-1	es-backup Options	174
TABLE 9-2	es-restore Options	177
TABLE 9-3	Sun Management Center Default Port Addresses	184
TABLE 9-4	es-config Options	186
TABLE 9-5	es-trapdest Options	189
TABLE B-1	es-uninst Options	214
TABLE B-2	es-inst Options	218
TABLE B-3	es-setup Options	229
TABLE C-1	Agent CPU and RAM Use Estimates by System Type	241
TABLE C-2	Hardware-Specific Module Availability	242
TABLE C-3	Sun Management Center Management Module System Impact Summary	243

TABLE C-4	Recommended Sun Management Center Server Hardware Platforms 246
TABLE C-5	PRM Configuration Type Requirements 248
TABLE C-6	Server Examples: Number of Agents under Management 249
TABLE C-7	Dedicated Host: Sun Fire Platform Agent Capacity 254
TABLE C-8	Server Layer Host: Sun Fire Platform Agent Capacity 255

Figures

FIGURE 1-1	Welcome Screen	30
FIGURE 1-2	Checking for Available Products Progress Bar	31
FIGURE 1-3	Add-on Products	31
FIGURE 1-4	Set Up Screen	33
FIGURE 1-5	SNMP Port Conflict Screen	35
FIGURE 1-6	Web Server Security Key Generation	37
FIGURE 1-7	Start Up the Product	38
FIGURE 1-8	Console Start Up	39
FIGURE 1-9	Sun Management Center Default Domain	39
FIGURE 2-1	Sun Management Center Basic Architecture	48
FIGURE C-1	Sun Management Center Server Load by Events per Day and Objects Managed	247
FIGURE C-2	Platform Agent Architecture	254
FIGURE D-1	Simple NAT Network Conceptual Diagram	259
FIGURE D-2	Simple NAT Network Configuration Example	262
FIGURE D-3	Complex NAT Network Configuration Example	264

Preface

The *Sun Management Center 3.6 Installation and Configuration Guide* tells you how to install and start the Sun™ Management Center system software.

Sun Management Center software can be deployed in two different environments:

- Production environment
- Developer environment

The *Production environment* is the runtime environment in which you manage and monitor your hardware, including subsystems, components, and peripheral devices.

The *Developer environment* is an environment in which developers can create and test customized modules for the Sun Management Center software. For more information on the Developer environment, refer to the *Sun Management Center 3.5 Developer Environment Reference Manual*.

Note – The Solaris™ 10 release supports systems that use the SPARC® and x86 families of processor architectures: UltraSPARC®, SPARC64, AMD64, Pentium, and Xeon EM64T. The supported systems appear in the *Solaris 10 Hardware Compatibility List* at <http://www.sun.com/bigadmin/hcl>. This document cites any implementation differences between the platform types.

In this document the term “x86” refers to 64-bit and 32-bit systems manufactured using processors compatible with the AMD64 or Intel Xeon/Pentium product families. For supported systems, see the *Solaris 10 Hardware Compatibility List*.

Who Should Use This Book

This book is for system administrators who understand networking terminology and have experience working with and maintaining networks.

How This Book Is Organized

This book contains the following information:

Chapter 1 describes the requirements for Sun Management Center 3.6 and how to install it for the first time.

Chapter 2 provides an overview of Sun Management Center 3.6 installation and licensing.

Chapter 3 provides information that should be considered before installing Sun Management Center 3.6, including security and Sun Management Center domain management approaches.

Chapter 4 provides procedures for preparing your systems before you upgrade to Sun Management Center 3.6, or install Sun Management Center 3.6.

Chapter 5 provides procedures for upgrading previous versions of Solstice SyMON™ or Sun Management Center to Sun Management Center 3.6.

Chapter 6 provides the procedures for installing and updating agents and installing Sun Management Center on Microsoft Windows.

Chapter 7 provides the procedures for post-installation tasks such as setting up users, installing multiple agents, upgrading agents, and installing separately released add-on products.

Chapter 8 provides the procedures for starting and stopping Sun Management Center.

Chapter 9 provides procedures for post-installation administration tasks, such as regenerating security keys, stopping and disabling the SNMP daemon, and reconfiguring port addresses.

Chapter 10 provides information that should be considered if you plan to integrate Sun Management Center with other management platforms.

Appendix A provides the procedures for uninstalling Sun Management Center 3.6 from the Solaris platform and the Microsoft Windows platform.

[Appendix B](#) provides the procedures for uninstalling, installing, and setting up Sun Management Center.

[Appendix C](#) provides information for determining the hardware resources needed by Sun Management Center.

[Appendix D](#) provides information about Network Address Translation (NAT) configuration and limitations, and provides configuration examples.

Product Information

Information about this product is located at the Sun Management Center Web site at <http://www.sun.com/sunmanagementcenter>.

The Sun Management Center product includes open source software. To view license terms, attribution, and copyright statements for open source software included in this release, see the copyright file available in the media.

Documentation, Support, and Training

Sun Function	URL	Description
Documentation	http://www.sun.com/documentation/	Download PDF and HTML documents, and order printed documents
Support and Training	http://www.sun.com/supporttraining/	Obtain technical support, download patches, and learn about Sun courses

Typographic Conventions

The following table describes the typographic changes that are used in this book.

TABLE P-1 Typographic Conventions

Typeface or Symbol	Meaning	Example
AaBbCc123	The names of commands, files, and directories, and onscreen computer output	Edit your <code>.login</code> file. Use <code>ls -a</code> to list all files. <code>machine_name%</code> you have mail.
AaBbCc123	What you type, contrasted with onscreen computer output	<code>machine_name%</code> su Password:
<i>aabbcc123</i>	Placeholder: replace with a real name or value	The command to remove a file is <code>rm filename</code> .
<i>AaBbCc123</i>	Book titles, new terms, and terms to be emphasized	Read Chapter 6 in the <i>User's Guide</i> . Perform a <i>patch analysis</i> . Do <i>not</i> save the file. [Note that some emphasized items appear bold online.]

Shell Prompts in Command Examples

The following table shows the default system prompt and superuser prompt for the C shell, Bourne shell, and Korn shell.

TABLE P-2 Shell Prompts

Shell	Prompt
C shell prompt	<code>machine_name%</code>
C shell superuser prompt	<code>machine_name#</code>
Bourne shell and Korn shell prompt	<code>\$</code>
Bourne shell and Korn shell superuser prompt	<code>#</code>

Using UNIX Commands

This document does not contain information about basic UNIX[®] commands and procedures such as shutting down the system, booting the system, and configuring devices.

For more information about UNIX commands and procedures, see the following documents:

- *Solaris Handbook for Sun Peripherals*
- Online documentation for the Solaris operating environment
- Other software documentation that you received with your system

Related Documentation

For details on Sun Management Center documentation and related Sun Management Center add-on documentation, see [“Sun Management Center Documentation Resources”](#) on page 43.

Installing Sun Management Center 3.6

This chapter describes how to install and set up Sun™ Management Center 3.6. This chapter assumes that the product has not been installed before.

This chapter has the following topics:

- “Installing the Product” on page 21
- “Preinstallation Information” on page 22
- “Sun Management Center Requirements” on page 25
- “Installing the Required JDK Version” on page 27
- “Sun Management Center Base Add-on Requirements” on page 27
- “Installing Sun Management Center” on page 29
- “Setting Up Sun Management Center” on page 33
- “(On Solaris 10) Monitoring a Zone Using Sun Management Center” on page 40
- “Sun Management Center Documentation Resources” on page 43

Installing the Product

Sun Management Center has three main components, called base layers, that need to be installed: server, agent, and Java™ Console (console). The server is a collection of processes on a central host that enables management services. The agent is a process that runs on each monitored host. The Java Console is the window through which you monitor and manage the agents. It is the main user interface to the product.

Before you can use Sun Management Center 3.6, you must install the

- Server – On at least one machine.

Note – When the server is installed, the Sun Management Center agent is installed on the server machine as well.

- Agent – On all machines you want to monitor.
- Java Console – On any machine from which users will log into Sun Management Center.

In planning your installation you need to consider the following items:

- On which machine do you want to run the Sun Management Center server?
- Which machines do you want to monitor and manage? On these machines you need to install the Sun Management Center agent.
- On which machines do you want to run the Sun Management Center console? On these machines you need to install the Java Console.
- Do you want to install the production environment or the developer environment? In a production environment you use Sun Management Center to manage and monitor your hardware. In a developer environment you use the product to develop and test modules to work with it. For more information on the production environment and the developer environment, see *Sun Management Center 3.5 Developer Environment Reference Manual*.
- Which add-on products do you want to use? Sun Management Center has add-on products to extend its feature set and to make it work with specific software products or hardware platforms. For more information on the product and how it works in these different environments, see the documentation listed in [“Sun Management Center Documentation Resources”](#) on page 43.

In addition to *installing* the product components and the add-ons, you must *set up* the product components and add-ons before you can start the product.

Preinstallation Information

The following table lists the prerequisite information that you need before installing the product.

TABLE 1-1 Information Needed Before Installing

Installation Item	Description
Environment	<p>Choose the <i>production</i> environment if you want to use the product to manage and monitor your hardware.</p> <p>Choose the <i>developer</i> environment to develop and test modules to work with the product. A machine used for development must meet the minimum hardware and software requirements for the server, agent, and console layers and any add-ons you install.</p> <p>Note – If you plan to install the developer environment, you should install it on a separate, dedicated machine. The server, agent, and console layers are automatically installed on a developer environment machine.</p>
Base Layers (Components)	Determine the machines on which you will install each component, for example, server, agent, and console.
Languages	<p>Determine which, if any, additional languages (French, Traditional Chinese, Simplified Chinese, Korean, or Japanese) you need.</p> <p>The documentation for Sun Management Center 3.6 is not available on the media. Go to http://docs.sun.com for documentation in English and the supported languages.</p>
Add-on Products	<p>Review the add-on supplements to determine which add-ons you want to install. For a list of add-on supplements, see “Sun Management Center Documentation Resources” on page 43.</p> <p>Add-on products are installed on the same machine as the server.</p>
Space Needed	<p>If the machine does not have enough space in the default <code>/opt</code> directory, you might need to make one of the following adjustments:</p> <ul style="list-style-type: none">■ Specify an alternate file system that has sufficient space■ Select a machine with sufficient resources■ Make more space in <code>/opt</code>
Permissions	You must have permission to write to the <code>/var/opt</code> and <code>/opt/SUNWsymon</code> directories as <code>root</code> on each machine. You also need privileges to run commands such as <code>chmod</code> .

After installing the product and its add-ons, you will need to set up the product and its add-ons. The following table lists the prerequisite information that you need before *setting up* the product.

TABLE 1–2 Information Needed Before Setting Up

Set Up Item	Description
Administrator user name	A valid Solaris/Linux user name is required for assignment as the Sun Management Center administrator on Sun Management Center server machines.
Network Addressing Mode	Sun Management Center uses two types of addressing for communication between the server and agent: IP addressing, and Network Address Translation (NAT). You must have the following information: <ul style="list-style-type: none">■ Which addressing mode is used in your network■ The name of each machine that is to be managed by Sun Management Center■ The IP addresses and names for all machines that have been assigned static IP addresses See Appendix D for further information.
Sun Management Center Password to Generate Security Key	Sun Management Center requires an encrypted security key for communication between processes. The security key is generated based on a unique password you provide. Store the password securely. You need the password if you modify your Sun Management Center installation.
SNMPv1 Community String	Sun Management Center requires an SNMPv1 community string for security. The default is <code>public</code> . You have the option of specifying a more secure custom string. Store the SNMPv1 string securely. You need the SNMPv1 security string if you modify your Sun Management Center installation.
Information to Generate Web Server Security Key	The Sun Management Center Web server requires an encrypted security key. The security key is generated based your organization name and location. Store the organization name and location securely. You need this information if you modify your Sun Management Center Web server.
Ports	Determine the assignments for the following ports: <ul style="list-style-type: none">■ SNMPv1 Port: default 161■ Sun Management Center Port: default 161, recommended 1161■ Database port: default 2521■ Web server port: default 8080■ Web server secure port: 8443 See “Default Ports” on page 183 for further information.

Sun Management Center Requirements

The following table provides a summary of Sun Management Center 3.6 requirements.

Note – Some hardware platform config readers (add-ons) do not work on all layers of Sun Management Center when installed on Solaris 10.

For specific information about determining the total amount of resources needed, see [Appendix C](#).

TABLE 1-3 Sun Management Center 3.6 System Requirements

Base Layer	Operating System	Disk Space	RAM	Swap
Server (SPARC)	Solaris 8, Solaris 9, and Solaris 10 Solaris Developer Software Group installation	800 Mbytes total: 300 Mbytes in /opt, 500 Mbytes in /var/opt	512 Mbytes minimum 1 Gbyte recommended for small to large servers 2 Gbytes recommended for extra-large servers.	1 Gbyte recommended
Agent (SPARC)	Solaris 2.6, Solaris 7, Solaris 8, Solaris 9, and Solaris 10 releases	18 Mbytes per agent in /opt/SUNWsymon. 2 Mbytes per agent in /var/opt/SUNWsymon.	10 to 29 Mbytes per agent depending on modules loaded and system type	
Agent (x86)	Solaris 9 and Solaris 10	18 Mbytes per agent in /opt/SUNWsymon. 2 Mbytes per agent in /var/opt/SUNWsymon.	10 to 29 Mbytes per agent depending on modules loaded and system type	

TABLE 1-3 Sun Management Center 3.6 System Requirements (Continued)

Base Layer	Operating System	Disk Space	RAM	Swap
Agent (Linux) on x86	RedHat Linux Enterprise 2.1 - 3.0 (32-bit and 64-bit), Sun Java™ Desktop System 2.x, SUSE Linux Enterprise 8.0 (32-bit and 64-bit), SUSE Professional 9 (32-bit and 64-bit)	18 Mbytes per agent in /opt/SUNWsymon. 2 Mbytes per agent in /var/opt/SUNWsymon.	10 to 29 Mbytes per agent depending on modules loaded and system type	
Java Console	Solaris 2.6, Solaris 7, Solaris 8, Solaris 9, and Solaris 10 releases	Solaris platform: 62 Mbytes	Solaris platform: 256 Mbytes	Solaris platform: 130 Mbytes
	Microsoft Windows 98, Microsoft Windows NT SP 4 or later, Microsoft Windows 2000 Professional, Microsoft Windows XP	Microsoft Windows platform: 35 Mbytes	Microsoft Windows platform: 256 Mbytes	Microsoft Windows platform: 768 Mbytes
	Linux 2.4.21 or higher	62 Mbytes	256 Mbytes	130 Mbytes

The default maximum heap size for the console and server is 64 Mbytes each.

Java console does not install jar files for add-ons.

You can customize the maximum heap size for the console and server as described in “Starting Components Using *es-start*” on page 167.

Installing the Required JDK Version

Sun Management Center 3.6 requires JDK™ 1.4.2 (minimum requirement), which is available on the `<DiskMountDir>/disk1/jdk_dir/TargetOS_dir` directory, where `jdk_dir` is the name of the JDK directory on the disk and `TargetOS_dir` is Linux or Solaris or Windows.

▼ To Install the Required JDK Version

Steps 1. **Install the JDK from the disk using the `pkgadd` command.**

Type the command `pkgadd -d <DiskMountDir>/disk1/jdk_dir`.

Press Return to install all of the packages. The JDK packages are installed in the `/usr/j2se` directory.

2. **Reset the `JAVA_HOME` environment variable to `/usr/j2se`.**

- In a C shell environment, type:

```
# setenv JAVA_HOME /usr/j2se
```

- In a Bourne or Korn shell environment, type:

```
# JAVA_HOME=/usr/j2se
# export JAVA_HOME
```

Tip – Set the `JAVA_HOME` environment variable in your `.login` or `.cshrc` file.

Sun Management Center Base Add-on Requirements

The following table shows the minimum disk space necessary to install the basic add-ons. For installation requirements for other add-ons, see the documentation supplement for that add-on. See [“Sun Management Center Documentation Resources” on page 43](#).

For specific information about determining the total amount of resources needed, see [Appendix C](#).

TABLE 1-4 Add-on Disk Space Requirements by Base Component

Base Add-on	Operating System	Disk Space
Advanced System Monitoring	Solaris 2.6, Solaris 7, Solaris 8, Solaris 9, Solaris 10 releases	Server: 3300 Kbytes Agent: 2020 Kbytes
	Windows 98, Windows NT, Windows 2000, Windows XP	Console: 270 Kbytes
Service Availability Manager	Solaris 2.6, Solaris 7, Solaris 8, Solaris 9, Solaris 10 releases	Server: 1600 Kbytes Agent: 1000 Kbytes Console: 500 Kbytes
Solaris Container Manager	Solaris 8, Solaris 9, Solaris 10 releases	Server: 300 Mbytes Agent: 18 Mbytes Console: 500 Kbytes
System Reliability Manager	Solaris 2.6, Solaris 7, Solaris 8, Solaris 9, Solaris 10 releases	Server: 3000 Kbytes Agent: 1000 Kbytes Console: not applicable
Performance Reporting Manager	Solaris 2.6, Solaris 7, Solaris 8, Solaris 9, Solaris 10 releases Windows 98, Windows NT, Windows 2000, Windows XP	Server: depends on reporting options selected. <ul style="list-style-type: none"> ■ Small configuration: 5 Gbytes ■ Medium configuration: 12 Gbytes ■ Large configuration: 24 Gbytes Agent: 8000 Kbytes minimum. For 1000 properties logged at five-minute intervals, 80 Mbytes are needed. Console: 3 Mbytes
Volume System Monitoring (VSM)	RedHat, SuSE Linux kernel version 2.4.x or higher, Solaris 9 or higher on SPARC and Solaris 10 or higher on i386.	<p>Note – The Performance Reporting Manager requires 1 Gbyte of RAM and 1 Gbyte of swap space.</p> <p>Note – This add-on can be installed only on hosts that has the Sun N1™ System Manager server installed.</p>

Installing Sun Management Center

Note – On Solaris 10, install Sun Management Center in the global zone. On Linux, you can install only agent and console layers.

This section describes how to install Sun Management Center 3.6 on Solaris and Linux platforms using the graphical user interface (GUI).

This installation procedure assumes that you are installing Sun Management Center from a cd-image directory on your network.

For information on creating an installation CD image, see [“Creating Installation CD Images” on page 85](#).

▼ To Install Sun Management Center

Steps 1. Set up the installation environment.

- a. If you are installing the product remotely, grant access to the X server by typing the command `xhost + machine` in a terminal window where *machine* is the name of the machine where you want to install the product.
- b. Log into the machine. If you are installing the product remotely, type the command `rlogin machine` and type the password.
- c. Log in as root by typing `su - root` and the root password.

Note – Do not miss the `'-'` after the `su` command

- d. If you prefer a specific UNIX shell, type the command to use the shell, for example, `csch`.
- e. If you are installing the product remotely, ensure that the `DISPLAY` environment variable is set to the machine's display, for example, `setenv DISPLAY local-machine:0.0`.
- f. Ensure that the group entry in the `/etc/nsswitch.conf` has `files` as the first token.

```
group: files nis
```

- g. **Change to the *cd-image* directory. Ensure that the *cd-image* directory is NFS-shared.**

For example:

```
# cd /net/machine/cd-image/disk1/sbin
```

where *machine* is the machine where you created the installation image, and *cd-image* is the root directory containing the installation CD images.

- h. **Review `disk1/sbin/README.INSTALL` and `disk1/sbin/INSTALL_README.HWDS`.**

2. Run the installation.

- a. **Change to the installation directory `<DiskMountDir>/disk1/sbin`.**

- b. **Type the installation command:**

```
# ./es-guiinst
```

The welcome screen appears.



FIGURE 1-1 Welcome Screen

3. Follow the screen prompts.

- a. **To accept the default `/opt` installation directory, click Next or click Browse to choose another directory.**
- b. **Select either the production environment or developer environment.**
This procedure assumes you have selected the production environment.
- c. **Select the components you want to install.**
- d. **Review the Server Layer Binary Code License and use the scroll bar to scroll down to the end of the text.**

- e. To agree to the terms of the license, click I Agree and click Next.
- f. If you want to install the product in additional languages, select the additional languages and click Next. The progress bar appears.




FIGURE 1-2 Checking for Available Products Progress Bar

- g. Select the add-on products.

The add-on products screen appears. Your list of add-on products might vary from this screen.




FIGURE 1-3 Add-on Products

- h. If you selected add-on products that have optional components, select the optional components required and click Next.
- i. Review the add-on products binary license and use the scroll bar to scroll down to the end of the text.
Some add-ons require binary license.
- j. To agree to the terms of the license, click I Agree and click Next.
The Checking Disk Space progress bar appears. If there is not enough disk space, you are asked to provide an alternate file system.

Tip – In a terminal window on the machine where you are installing Sun Management Center, type `df -ak` to list the amount of used and free space for each file system on the machine.

- k. Confirm installation selections and click Next.

Note – The installation process can take from a few minutes to half an hour or more, depending on the products selected.

If installation failed, a summary screen is displayed.

Review the installation log in `/var/opt/SUNWsymon/install` to find out why the installation failed, and correct the problem.

4. Choose whether to run the setup wizard.



Caution – If you have used `gui-inst` to install only add-on products, click Close to exit the installation and setup process. You must set up the add-on products as described by [“To Set Up an Add-on Product Using `es-setup`”](#) on page 162. Otherwise, you will overwrite your security keys and will then have to set up all of the agents on all of your machines for the agents to work properly.

- a. To continue to set up, click Next.
- b. To run set up later, click Close.
You cannot run the product until you have set it up.

Setting Up Sun Management Center

You use the graphical setup wizard to set up, configure, and re-configure your Sun Management Center installation.

For information on using the command-line setup script, see [“To Set Up Sun Management Center Using the es-setup Script”](#) on page 231.

▼ To Set Up Sun Management Center

Steps 1. **Set up the installation environment. For more information, see Step 1 in “To Install Sun Management Center” on page 29.**

2. **Change to the Sun Management Center `sbin` directory. For example:**

```
# cd /opt/SUNWsymon/sbin
```

If you installed Sun Management Center in a directory other than `/opt`, Change to `/installdir/SUNWsymon/sbin`, where `installdir` is the directory you specified.

3. **Run the set up by typing:**

```
# ./es-guisetup
```

The Set Up screen appears.



FIGURE 1-4 Set Up Screen

4. **Follow the screen prompts.**

a. **You are given the opportunity to store all of your setup responses in the file `/var/opt/SUNWsymon/install/setup-responses-file`. The**

setup-responses-file file is useful if you need to duplicate the setup on the current machine on other machines.

- To continue setup without creating the response file, click Next.
- To create the response file, select Store Response Data and then click Next.

b. Generate the Sun Management Center security key.

Type a password in both fields and click Next to generate the security keys.

An encrypted security key is needed for communications between all Sun Management Center processes. The key is generated based on the password you provide, which must be between one and eight characters long and contain no spaces. Entries that are greater than eight characters are truncated to eight characters.

Note – Keep a record of the password you use to generate the security key for this machine in a secure location. You might need to regenerate the key for the machine at a later time. You can also change the security key later, if needed, as described in [“Regenerating Security Keys”](#) on page 178.

c. Specify the SNMPv1 community security string.

The community string is used for SNMP security and is set to `public` by default.

Set the community string to a value other than `public` or `private` to provide better SNMP security.



Caution – The same SNMP community string must be used on all of the machines on which you install Sun Management Center. If you use different community strings on each machine, SNMP communications between the machines and Sun Management Center components will not work.

- If you want to accept the community string default value of `public`, click Next.
- If you want to use a custom community string:
 - a. Select Use Custom Community String.

The community string can be up to 255 characters and must not contain any spaces or blanks.
 - b. Type the same community string in both fields, and then click Next.

d. Enter a valid Solaris/Linux user name as the UNIX administrator account and click Next.

The setup process checks whether the SNMP port is in use.

e. If the SNMP port is in use, the SNMP Port Conflict screen appears.



FIGURE 1-5 SNMP Port Conflict Screen

f. **Resolve the port conflict.**

In most cases, port 161 is the default port assigned to and used by the SNMP daemon. However, other processes or daemons could be using port 161. Several third-party replacements and enhancements for the SNMP daemon exist and could be installed on your system. The Sun Management Center agent is such a daemon.

We recommend that you use a different port number, such as port 1161.

- To assign a different port number to Sun Management Center:
 - a. Click Use a Different Port Number.
For instructions on how to find out whether a port is used, see [“To Determine Whether a Port Is Used”](#) on page 184.
 - b. Type the port number, for example, 1161, in the Port ID field and click Next.

Note – Keep a record of this alternate port number. You will need this number if you later install agents using JumpStart or update the Sun Management Center agents using the agent update-image tools.

- To use port 161, select Use Port 161 and click Next.
- g. **If you use port 161, you are reminded to manually stop and disable the SNMP daemon `snmpdx`.**

Note – (On Solaris 10) If you use port 161, you will be reminded to stop and disable the SNMP daemon *SMA* manually.

There is no SNMP daemon on Linux by default.

- To stop and disable the SNMP daemon `snmpdx` automatically, make sure that Stop and Disable SNMP Daemon `snmpdx` has been selected, and then click Next.



Caution – Stopping and disabling the system SNMP daemon does not guarantee that you have stopped the actual process using port 161. To determine the actual daemon process that uses port 161, you must manually review all `/etc/rcN` and `/etc/rcN.d` files, where *N* is 0 through 6 and *S*. When you have identified the file that defines the process using port 161, you can disable the process by renaming the file. For example,

```
/etc/rc3.d# mv S76snmpdx s76snmpdx
```

You must stop all other processes that use port 161 before you can start Sun Management Center.

- To stop and disable the SNMP daemon *SMA*, navigate to the `/etc/init.d` directory. Type `./init.sma stop`.

h. If any Sun Management Center ports are in use, you are prompted to resolve the port conflict.

The ports are checked in the following order: trap service, event service, topology service, configuration service, platform agent, `cst` service, metadata service, database, look-up service, Web server default port, and Web server secure port.

If any of the ports are in use, you are prompted to provide an unused port number. Type an unused port number in the field, and then click Next.

i. Generate the Web server security key.



FIGURE 1-6 Web Server Security Key Generation

An encrypted security key is needed for the Sun Management Center Web server. The key is generated based on the name of your organization and the name of your location. The names that you provide must not contain any spaces or blanks.

Type the name of your organization and the name of your location to generate the Web server security key and click Next.

For example, you could type `admin` in the Name of Your Organization field and `headquarters` in the Name of Your Location field.

Note – Keep a record of the entries you use to generate the security key in a secure location in case you need to regenerate the key for a particular machine at a later time.

j. Confirm setup selections.

The setup process can take from a few minutes to half an hour or more, depending on the products selected.

If base product setup failed, you are informed that the setup of the base products was not successful. You are directed to see the log file for more details. The name of the log file is provided.

k. If you installed add-ons, click Next to set them up.

Some add-on products are included with the Sun Management Center 3.6 installation CDs. These add-ons are the ones listed in the Select Add-on Products panel. For information on how to set up each add-on, refer to the Sun Management Center supplement for each add-on. Each supplement provides the setup procedure for the specific add-on.



Caution – If you selected the add-on Monitoring and Management of A5x00 and T3 Devices, make sure you apply the necessary patches to the server as described in [“Sun StorEdge A5x00 Packages” on page 81](#). Also, add each T3 IP address, Ethernet address, and name to the server system files, as described in [“T3 Storage Devices” on page 81](#).

1. **Start the product by selecting the components to start and clicking Next.**
For more information on starting and stopping Sun Management Center, see [Chapter 8](#).



Caution – If your network uses Network Address Translation (NAT), click Close. Use the `es-config` command-line utility described in [“To Enable NAT Support” on page 197](#) to configure the machine for NAT before you start Sun Management Center.



FIGURE 1-7 Start Up the Product

5. **Start the console by typing this from a terminal window: `./es-start -c&`.**
The Java Console login screen appears.



FIGURE 1-8 Console Start Up

Tip – If help does not come up in Java Console, modify the browser path in the `javaconsole.properties` file. This file is available in `/var/opt/SUNWsymon/cfg/` if you have installed the console layer. Otherwise, this file will be available in `/opt/SUNWsymon/cfg/`.

You are prompted to select the default domain and then a screen similar to this appears.




FIGURE 1-9 Sun Management Center Default Domain

Note – (On Solaris 10) When Sun Management Center is installed and set up, the services run as Service Management Facility (SMF) services. Based on the layers chosen, appropriate services will be started.

For information on using the product, see *Sun Management Center 3.6 User's Guide*.

(On Solaris 10) Monitoring a Zone Using Sun Management Center

Zone is a virtualized operating system environment that you can set up for systems that run the Solaris 10 Operating System. Every Solaris system contains a global zone, the default zone for the system. You can create local (non-global) zones. You can monitor a zone by running an agent inside a local zone.

▼ To Create a Local Zone

You can create a local zone either through zone commands or through the zone wizard of Solaris Container Manager.

If you create a local zone using Solaris Container Manager, ensure that you add the base directory of Sun Management Center to the `inherit-pkg-dir` directory. You can specify this in the "Provide Inherit Package" step of the wizard.

For more information, see "Managing Zones" in *Installing and Administering Solaris Container Manager 1.1*.

Step ● Create a local zone using zone commands.

a. Become superuser and open two terminal windows.

b. From the first terminal window, type the following lines to create a local zone.

```
#zonecfg -z localzonename, where localzonename is the name of the local zone.
```

```
No such zone configured Use 'create' to begin configuring a new zone.
```

```
zonecfg:localzonename> create
```



```

zonecfg:localzonename> export
zonecfg:localzonename> add inherit-pkg-dir
zonecfg:localzonename:inherit-pkg-dir> set dir=/opt, where /opt is the
installation directory.
zonecfg:localzonename:inherit-pkg-dir> end
zonecfg:localzonename> add net
zonecfg:localzonename:net> set address=ipaddress
zonecfg:localzonename:net> set physical=networkinterface
zonecfg:localzonename:net> end
zonecfg:localzonename> set zonepath=/export/zone/localzonename
zonecfg:localzonename> verify
zonecfg:localzonename> commit
zonecfg:localzonename> exit
#zoneadm -z localzonename install

```

c. **From the second terminal window, type `zlogin -C localzonename` to log in to the local zone**

d. **From the first terminal window, type `zoneadm -z localzonename boot` to boot the zone.**

The boot messages are displayed in the second terminal window where you logged in to the zone.

e. **Type the appropriate values for locale, terminal type, host name, naming service etc.**

The zone will be rebooted.

▼ To Use an Existing Local Zone

This procedure assumes that the local zone does not inherit `/opt/SUNWsymon` and that the path of the local zone is `/export/zone/localzonename`.

Steps 1. **Become superuser.**

2. **From the terminal window, log in to the local zone.**

```
zlogin localzonename mkdir -p /opt/SUNWsymon
```

3. Do a loopback mounting of `/opt/SUNWsymon`.

```
mount -F lofs /opt/SUNWsymon
/export/zone/localzonename/root/opt/SUNWsymon
```

▼ To Monitor a Zone Using Sun Management Center

Before You Begin Install and set up Sun Management Center in the global zone.

- Steps**
1. Create a local zone as described in [“To Create a Local Zone” on page 40](#) or use an existing local zone as described in [“To Use an Existing Local Zone” on page 41](#).

2. From the global zone, set up an agent to run inside this local zone.

```
/opt/SUNWsymon/sbin/es-setup -z localzonename
```

3. From the global zone, log in to the local zone.

```
zlogin localzonename
```

4. From the local zone, complete the setup.

```
/opt/SUNWsymon/sbin/es-setup
```

Supported Commands, Modules, and Add-ons

You can start and stop the agent from within the local zone. You can use `es-config` to change the port number of the agent.

The commands supported inside the local zone are `es-start`, `es-stop`, `es-setup`, `es-config`, and `es-load-default`.

The list of modules that will be available for the agent inside the local zone is available at `/var/opt/SUNWsymon/cfg/zone-modules-d.dat`. If you remove a module from this file, that module will not be available when the agent is restarted.

This release supports setting up and running of Advanced System Monitoring, Service Availability Manager, System Reliability Manager, and Performance Reporting Manager inside a local zone.

Note – Java Console is not supported inside a local zone.

Sun Management Center Documentation Resources

Sun Management Center works in *production* and *developer* environments. It also has many add-on products. For more information on the product and how it works in these two environments, see the documentation listed in the following table.

For updated information on documentation resources, see the *Sun Management Center 3.6 Installation and Configuration Guide*.

Note – Documentation for Sun Management Center is *not* installed with the product. The documents are available at <http://docs.sun.com>.

TABLE 1-5 Documentation Resources

Environment	Documentation	
If you install and use the product in a <i>production</i> environment, see	<i>Sun Management Center 3.6 User's Guide</i> - Describes how to use the product.	
	<i>Sun Management Center 3.6 Installation and Configuration Guide</i> - Describes how to install and configure the product.	
If you use the product in a <i>developer</i> environment, see	<i>Sun Management Center 3.5 Developer Environment Reference Manual</i>	
If you use the product with <i>other software products or add-ons</i> (listed alphabetically), see	Advanced System Monitoring	Not Applicable
	Hardware Diagnostic Suite 2.0	<i>Hardware Diagnostic Suite 2.0 User's Guide</i>
	Solaris Container Manager 3.6	<i>Solaris Container Manager 3.6 Release Notes</i>
		<i>Installing and Administering Solaris Container Manager 3.6</i>
	Performance Reporting Manager	<i>Sun Management Center 3.5 Update 2 Performance Reporting Manager User's Guide</i>
	Service Availability Manager	<i>Sun Management Center 3.5 Service Availability Manager User's Guide</i>

TABLE 1-5 Documentation Resources (Continued)

Environment	Documentation
Sun Cluster	Task Map: Installing the Sun Cluster Module for Sun Management Center in the <i>Sun Cluster Software Installation Guide for Solaris OS</i>
System Reliability Manager	Sun Management Center 3.6 System Reliability Manager User's Guide
Tivoli TEC Adapter	<i>Sun Management Center Tivoli TEC Adapter Installation Guide</i>
Unicenter TNG	<i>Sun Management Center CA Integration Package User's Guide for Unicenter TNG</i>
If you use the product with these <i>hardware platforms</i> (listed alphabetically), see	
ELP Config Reader (CommonConfigReader)	See Sun Fire™ V210/V240/V250/V440/1500/2500
Desktop	See Sun Blade™ 100/150/1000/1500/2000/2500
Dynamic Reconfiguration for Sun Fire high-end and midrange	See Sun Fire V880/V890/15K to 3800
hPCI+ board and CP2140 system controller for Sun Fire high-end systems	See Sun Fire high-end systems
Netra™ 20/120/1280	<i>Sun Management Center 3.5 Supplement for Netra Servers</i>
Netra 240/440	<i>Sun Management Center 3.6 Supplement for Sun Fire, Sun Blade and Netra Systems</i>
Netra T4/20	<i>Sun Management Center 3.5 Supplement for Netra Servers</i>
PCI+ support for Sun Fire midrange systems	See Sun Fire midrange systems
Sun Blade™ 100/150/1000/2000	<i>Sun Management Center 3.5 Supplement for Workstations</i>
Sun Blade 1500/2500	<i>Sun Management Center 3.6 Supplement for Sun Fire, Sun Blade and Netra Systems</i>
Sun Cobalt™ LX50	See the software product, Sun Management Center Linux Agent
Sun Fire V60x/V65x/V20z/V40z	See the software product, Sun Management Center Linux Agent
Sun Fire 280R/V480/V490/V880/V890	<i>Sun Management Center 3.5 Supplement for VSP High-End Entry Servers (Workgroup Servers)</i>

TABLE 1-5 Documentation Resources (Continued)

Environment	Documentation
Sun Fire high-end E25K/E20K/15K/12K	<i>Sun Management Center 3.5 Version 6 Release Notes and Supplement for Sun Fire High-End Systems</i>
Sun Fire midrange E6900/E4900/6800/4810/ 4800/3800	<i>Sun Management Center 3.5 Version 6 Release Notes and Supplement for Sun Fire Midrange Systems</i>
Sun Fire entry-level midrange E2900	<i>Sun Management Center 3.5 Version 6 Release Notes for Sun Fire Entry-Level Midrange Systems</i> <i>Sun Management Center 3.5 Version 6 Supplement for Sun Fire Entry-Level Midrange Systems</i>
Sun Fire V100/V120	<i>Sun Management Center 3.5 Supplement for Netra Servers</i>
Sun Fire V210/V240/V250/V440	<i>Sun Management Center 3.6 Supplement for Sun Fire, Sun Blade and Netra Systems</i>
Sun LX50	See the software product, Sun Management Center Linux Agent
Sun StorEdge™ A5x00/T3	<i>Sun Management Center 3.5 Supplement for the Sun StorEdge A5x00 and T3 Arrays</i>
UltraSPARC® IV CPU board support for Netra 1280	Requires midrange systems firmware 5.17.0 and Netra-T add-on packages for Sun Management Center
UltraSPARC IV CPU board support for Sun Fire 6800/4800	See Sun Fire 6800/4800

Installation Overview

This chapter provides overviews and examples of the installation and setup process. This chapter also provides a brief overview of the Sun Management Center and its components. Sizing information is provided in [Appendix C](#).

This chapter discusses the following topics:

- [“Sun Management Center Overview”](#) on page 47
- [“Supported Platforms”](#) on page 53
- [“Sample Sun Management Center Fresh Installation”](#) on page 55
- [“Sun Management Center 3.0 to Sun Management Center 3.5 Update 2”](#) on page 58
- [“Sun Management Center 2.1.1 to Sun Management Center 3.5 Update 2 Upgrade”](#) on page 60
- [“Using Agent-Update to Upgrade Agents to Sun Management Center 3.6”](#) on page 63
- [“To Install the Sun Management Center Console on Microsoft Windows”](#) on page 64
- [“Product Documentation”](#) on page 64

Sun Management Center Overview

Sun Management Center software is an open and extensible system management tool that enables you to:

- Perform remote configuration
- Monitor performance
- Isolate hardware and software faults

The Sun Management Center product is divided into a set of three base components. This section discusses the following topics:

- “Sun Management Center Architecture and Base Components” on page 48
- “Sun Management Center Base Add-on Products” on page 49
- “Additional Add-on Products” on page 50
- “Developer Environment” on page 50

The installation and setup of all Sun Management Center software, including add-on products, can be performed with a single installation command as described briefly in Chapter 1 and in greater detail in Chapter 6.

Sun Management Center Architecture and Base Components

The Sun Management Center software management framework is based on a three-tier architecture consisting of the Sun Management Center console, server, and agent components, which provide the core Sun Management Center functions.




FIGURE 2-1 Sun Management Center Basic Architecture

- The Server executes management tasks and sends requests to Sun Management Center agents to perform management tasks. The server stores network hardware and software information as well as network and Sun Management Center configuration in a database. The Sun Management Center server is normally installed on a single dedicated machine, and only one Sun Management Center server is required on a network.
- The Agent responds to the Sun Management Center Server directives, accesses management information on the local machine, provides alarm determination, and monitors local resources. The agent is automatically installed on the Sun Management Center server machine and must be separately installed on any machine that you wish to monitor.
- The Java Console is the graphical user interface that you use to monitor your network and run network management tasks.

- The web console is an alternate user interface to the Java Console and has a subset of the Java Console's features.
- The Sun Management Center Web server is installed with the server layer on the same host as the server layer.

The Web Server enables you to access the Sun Management Center web console from any system that supports either one of the following Web browsers.

- Netscape Navigator™ 6.0 or higher
- Internet Explorer 5.5 or higher
- Mozilla™ 1.4 or higher

Sun Management Center initiates operations by sending requests to the Sun Management Center agents installed on each system. Based on SNMP technology, the agents process server requests. The agents also act autonomously, collecting and processing data locally. Agents can act on observed conditions to send SNMP traps (messages sent when errors or specific events occur on the network) or execute management operations. The agents can raise alarms or initiate specific actions through customized rules and thresholds even when connection to the manager is severed. For further information about SNMP, see [“Security Keys and SNMP Community String” on page 68](#) and [“SNMP Daemons and Legacy Agents” on page 180](#).

Management and monitoring functions of the Sun Management Center agent are structured into loadable modules. The agent modules provide flexibility, enabling you to establish as little or as much monitoring and management as required on a per system basis. Additional modules can be dynamically loaded into Sun Management Center agents from the Sun Management Center console without disruption of the management or agent systems. For further information about Sun Management Center modules, see Appendix C, *“Sun Management Center Software Modules,”* in *Sun Management Center 3.6 User's Guide*

Sun Management Center Base Add-on Products

Sun Management Center provides four add-ons that are distributed as part of the Sun Management Center distribution on CD or the Web download image:

- **Advanced System Monitoring** - Provides full kernel reader functionality, Solaris health monitoring, file system monitoring, directory size monitoring, process monitoring, IPv6 protocol monitoring, MIB-II Instrumentation, and log viewing.
- **Performance Reporting Manager** - Adds analysis, reporting, and graphing capabilities.
- **Service Availability Manager** - Tests and measures the availability of network services including DNS and NIS naming services, Web server, directory, LDAP, Telnet, FTP, mail, and Solaris calendar services.
- **System Reliability Manager** - Enhances reliability, helping to increase service levels and decrease administrative costs.

For detailed information about base add-on and additional add-on products, see the Sun Management Center Web site at <http://www.sun.com/software/solaris/sunmanagementcenter/>.

Additional Add-on Products

Depending on the hardware platform on which you are installing Sun Management Center software, your system might require additional platform-specific add-ons. The add-on products provide additional functionality such as additional support for specific Sun hardware architectures, configuration readers, and new agent management. For information about a specific hardware platform, see the Sun Management Center supplement for your hardware platform. For information about additional add-ons for Sun Management Center, see the Sun Management Center Web site.

Note – You should always read your Sun Management Center supplement for architecture-specific installation instructions before installing Sun Management Center software on a particular hardware platform.

Add-on products are released in one of two ways:

- As part of the Sun Management Center distribution (CD or Web download image)
- Separately (add-on product only)

Add-on products released as part of the Sun Management Center distribution are installed during the installation process. The basic components are installed first, followed by installation of the add-on products.

Many add-on products offer architecture-specific support. Therefore, the installation checks your hardware. For example, if an add-on product supports workstation systems, you are given the opportunity to install the workstation add-on when you install Sun Management Center on a workstation host. In most cases, user confirmation is required prior to installing an add-on product.

If the add-on product is released separately from the Sun Management Center CD distribution, the add-on product includes its own installation instructions in the accompanying supplement.

Developer Environment

The developer environment enables you to extend Sun Management Center software functionality in various ways. You can perform the following tasks:

- Create custom management modules

- Create client programs that interface with Sun Management Center
- Integrate applications with the Sun Management Center console

Note – If you are installing the developer environment, you should run the Sun Management Center 3.6 developer environment and the Sun Management Center 3.6 production environment on separate, dedicated servers.

For further information about the Sun Management Center 3.6 developer environment, see the *Sun Management Center 3.6 Developer Environment Reference Manual*.

Sun Management Center Directories

After a successful installation and setup on the Solaris platform, directories are created as shown in [Table 2-1](#).

On Microsoft Windows, only the `C:\Program Files\SunMC` directory is created.

TABLE 2-1 Sun Management Center Default Solaris Directories

Directory	Description
<code>/opt/SUNWsymon</code>	Root directory that contains the infrastructure and applications of Sun Management Center
<code>/etc/opt/SUNWsymon</code>	Contains the <code>init</code> scripts for Sun Management Center software applications
<code>/var/opt/SUNWsymon</code>	Contains the Sun Management Center configuration and data files for your system
<code>/usr/apache/tomcat</code>	Contains the Web server. The Web server is installed with the Sun Management Center server
<code>/var/apache</code>	Web server documentation and examples

Sun Management Center System Files

This section describes the system files modified by installation of Sun Management Center, and provides an overview of operating system patches.

/etc/system File

The values listed in the `/etc/system` file are the default values for Sun Management Center system parameters. The `shmmax` value is computed based on the available RAM on the machine.

The Sun Management Center software installation checks whether the limits in the `/etc/system` file are sufficient for the services layer to perform as expected. For example, the following entries are added to the `/etc/system` file if the entries are absent. If the values present are inadequate, the values are updated accordingly.

```
*****
* This file has been modified by Sun MC 3.6 setup. *
*   DO NOT REMOVE THESE TWO COMMENT LINES.   *
*****
set shmsys:shminfo_shmmax=201326592
set shmsys:shminfo_shmmin=1
set shmsys:shminfo_shmmni=100
set shmsys:shminfo_shmseg=10
set semsys:seminfo_semmni=100
set semsys:seminfo_semmns=115
set semsys:seminfo_semmns=200
set semsys:seminfo_semopm=100
set semsys:seminfo_semvmx=32767
```

If any of the `/etc/system` entries are changed by the Sun Management Center software installation, then the system must be rebooted before proceeding further. After the system has rebooted, you must rerun the setup process using either `es-setup` or `es-guisetup`.

If `/etc/system` was changed by a previous installation of the Sun Management Center software, a system reboot is not necessary.

/etc/group File

The Sun Management Center software installation program adds the groups `esadm`, `esdomadm`, and `esops` to the local `/etc/group` file on the machine. A group entry is created for the database group `smcorag` in `/etc/group` on the machine where the Sun Management Center server is installed.

The user specified as the administrator during Sun Management Center setup is added to the `esadm` and `esdomadm` groups. For example, if the root user account is specified as the Sun Management Center administrator, the installation program appends the following lines to `/etc/group`:

```
smcorag::101011:
esadm::1000:root
esdomadm::1001:root
esops::1002:
```

`/etc/passwd` File

The Sun Management Center software installation adds the user `smcorau` to the `/etc/passwd` file. The `smcorau` user account is needed to run the database on the Sun Management Center server layer.

`/var/opt/SUNWsymon/cfg/esusers` File

The `/var/opt/SUNWsymon/cfg/esusers` file is used to define authorized Sun Management Center users. For further information, see [“Users, Groups, and Roles Overview”](#) on page 65.

Supported Platforms

For the latest information on supported hardware platforms, see the Sun Management Center Web site at <http://www.sun.com/sunmanagementcenter>.

Sun Management Center uses modules to monitor and manage the resources of systems, applications, and network devices. The module defines a collection of objects to be monitored by the agent. The Config-Reader module is required for hardware configuration information.

The following table provides examples of supported platforms for Sun Management Center and its add-ons.

TABLE 2-2 Examples of Supported Platforms

Operating System	Sun Management Center Layers	Example Hardware
Solaris (SPARC)	Agent, console, server, add-ons Note – Some add-ons are platform-specific.	<ul style="list-style-type: none"> ■ Small server Agents: 1 to 250 nodes Processor: Single 550/650 MHz UltraSPARC® Ili processor or higher Memory: 1 GB RAM or higher Examples: Sun Fire V100/V120 ■ Medium server Agents: 250 to 500 nodes Processor: Single 1.5 GHz UltraSPARC® IIIi processor or higher Memory: 2 GB RAM or higher Examples: Sun Blade 1500 ■ Large server: Agents: 500 to 750 nodes Processor: Two 1.34 GHz UltraSPARC® IIIi processors or higher Memory: 2 GB RAM or higher Examples: Sun Fire V210/V240, Sun Blade 2500 ■ Extra-large server: Agents: 750 to 1000 nodes Processor: Four 1.28 GHz/1.5 GHz UltraSPARC® IIIi processors or higher Memory: 2 GB RAM or higher Examples: Sun Fire V440/V480/V490
Solaris (SPARC)	Agent, console, add-ons Note – Some add-ons are platform-specific.	<ul style="list-style-type: none"> ■ SPARCStation 1/ 2/ 5/10/ 20 ■ Ultra 1/450 ■ Sun Blade 100/1000 ■ Netra AC200/1120/1125/1400/1405 ■ Sun Enterprise 150/3000/4000/5000/6000 ■ Sun Ultra Enterprise 150/3000/4000/5000 ■ Sun Fire 280R/V880/3800/4800/4810/6800/15000 ■ SPARCcenter® 2000/2000E/1000/1000E
Solaris (x86), Linux	Agent, console, some add-ons	<ul style="list-style-type: none"> ■ Sun Fire V60x/V65x ■ Sun Fire V20z ■ Sun Fire V40z

TABLE 2-2 Examples of Supported Platforms (Continued)

Operating System	Sun Management Center Layers	Example Hardware
Solaris, Windows 98, Windows NT, Windows 2000, Windows XP	Console layer and some add-ons	Pentium 233 MHz or better

The Config-Reader and the Dynamic Reconfiguration modules are not supported on all Sun hardware platforms. However, all other base Sun Management Center modules are supported on Sun hardware platforms.

For more information on base modules, refer to the *Sun Management Center 3.6 User's Guide*.

Sample Sun Management Center Fresh Installation

The following sample scenarios provide summaries of the major steps required to install Sun Management Center for the first time and to upgrade previous versions of Sun Management Center to Sun Management Center 3.6.

Note – To install, upgrade, and set up Sun Management Center, you must log in as root on each machine.

In this example, the Sun Management Center server, agent, console, and the Advanced System Monitoring (ASM) add-on are to be installed on three machines as follows:

- The console is to be installed on machine A. The ASM add-on is to be installed machine A.
- The server is to be installed on machine B. The ASM add-on is to be installed machine B.
The agent is automatically installed with the server.
- The agent is to be installed on machine C. The ASM add-on is to be installed machine C.

Sun Management Center has not been installed on any of the machines.

The following procedure summarizes the major steps required to install Sun Management Center and ASM.

▼ To Install Sun Management Center and ASM

- Steps**
- 1. Make sure each machine is a supported platform.**
See [“Supported Platforms”](#) on page 53.
 - 2. Make sure each machine has the required resources.**
See [“Preinstallation Checklist”](#) on page 74.
 - 3. Determine whether you will install from the CDs or from a CD image.**
See [“Determining the Installation Source”](#) on page 85.
 - 4. Install the server on machine B as described in [“Installing Sun Management Center”](#) on page 29.**
During installation:
 - Select the production environment.
 - Select the server layer only. The agent layer is automatically selected.
 - Select the Advanced System Monitoring add-on.
Advanced System Monitoring enables advanced monitoring capabilities for the server machine. For further information, see [“Additional Add-on Products”](#) on page 50.

When installation is finished, you are informed that the `/etc/system` file has been updated, and that the system must be rebooted. Exit the installation process, and reboot the system.
 - 5. Set up the Sun Management Center server on machine B.**
When the system has rebooted, type the command `/opt/SUNWsymon/sbin/es-guisetup` to set up the Sun Management Center server.
When setting up the server:
 - Provide a password to generate the security key.
The password must be the same for all Sun Management Center machines.
 - Provide an SNMPv1 security string.
The security string must be the same for all Sun Management Center machines.

When server setup is finished, the Advanced System Monitoring setup is performed.

When Advanced System Monitoring setup is finished, you are given the option to start Sun Management Center components. Start all components.
 - 6. Install the agent on machine C as described in [“Installing Sun Management Center”](#) on page 29.**
During installation:

- Select the production environment.
- Select the agent layer only.
- Select the Advanced System Monitoring add-on.
Advanced System Monitoring enables advanced monitoring capabilities for the agent machine. For further information, see [“Additional Add-on Products” on page 50](#).

Note – If you need to install the agent on several machines, you can create an agent-update image and install the agent using the image as described in [New LINK](#).

When the agent installation is finished, you are given the option to run setup. Run setup.

7. Set up Sun Management Center agent on machine C.

When setting up the agent:

- Provide the same security key password that you provided in [Step 5](#).
- Provide the same SNMPv1 community string that you provided in [Step 5](#).
- Provide the name of the Sun Management Center server machine.

When agent setup is finished, you are given the option to start the Sun Management Center agent. Start the agent.

8. Install the console on machine A as described in [“Installing Sun Management Center” on page 29](#).

During installation:

- Select the production environment.
- Select the console layer only.
- Select the Advanced System Monitoring add-on.
Advanced System Monitoring includes console components and menus.

When the console installation is finished, you are given the option to run setup. Run setup.

When setup is finished, start the console by typing the command
`/opt/SUNWsymon/sbin/es-start -c`.

Sun Management Center 3.0 to Sun Management Center 3.5 Update 2

In this example, the Sun Management Center 3.0 server, agent, and console are installed on three machines as follows:

- The Sun Management Center 3.0 console is installed on machine A.
- The Sun Management Center 3.0 server is installed on machine B.
- The Sun Management Center 3.0 agent is installed on machine C.

The following procedure summarizes the steps required to upgrade the Sun Management Center 3.0 installation to Sun Management Center 3.5 Update 2 on all three machines.

Note – If your Sun Management Center 3.0 installation includes the Performance Reporting Manager, the upgrade process enables you to migrate the Sun Management Center data and your Performance Reporting Manager data. Make sure the machine on which the Performance Reporting Manager is installed has sufficient resources for the Sun Management Center 3.5 Update 2 as described in [Table 1-4](#).

▼ To Upgrade Sun Management Center 3.0 to Sun Management Center 3.5 Update 2

- Steps**
1. **Make sure each machine is a supported platform.**
See [“Supported Platforms”](#) on page 53.
 2. **Make sure each machine has the required resources.**
See [“Preinstallation Checklist”](#) on page 74.
 3. **Determine whether you will install from the CDs or from a CD image.**
See [“Determining the Installation Source”](#) on page 85.
 4. **Install the Sun Management Center 3.5 Update 2 server on machine B as described in [“Upgrading the Server”](#) on page 95.**
During the installation:
 - Uninstall the previous Sun Management Center version when prompted.
 - Choose whether to migrate the Sun Management Center version data.
 - Select migrate data to save your Sun Management Center 3.0 data and use the data in Sun Management Center 3.5 Update 2.

- Select discard data if you do not want to save your Sun Management Center 3.0 data.
- Select the production environment.
- Select the server layer only. The agent is automatically installed.

When server installation is finished, you are given the option to run setup. Run setup.

5. Set up the server on machine B.

During server setup:

- Provide a password to generate the security key.
The password must be the same password you provided when you set up Sun Management Center 3.0.
- Provide an SNMPv1 security string.
The security string must be the same security string you provided when you set up Sun Management Center 3.0.
- If you chose to migrate the Sun Management Center 3.0 data to Sun Management Center 3.5 Update 2, choose whether to restore the Sun Management Center 3.0 data.

Note – If you provide a different password for security seed generation on the server than you provided for Sun Management Center 3.0, then you must use the new password to generate the same security seed when setting up the agents. If you do not upgrade a Sun Management Center 3.0 agent to Sun Management Center 3.5 Update 2, you must regenerate the security key for the Sun Management Center 3.0 agent machine as described in [“Regenerating Security Keys” on page 178](#).

When server setup is finished, you are given the option to start Sun Management Center components. Start all components.

6. Install the Sun Management Center 3.5 Update 2 agent on machine C as described in [“Upgrading Agents” on page 98](#).

During agent installation:

- Choose whether to migrate the Sun Management Center version agent data.
 - Select migrate data to save your Sun Management Center 3.0 data and use the data in Sun Management Center 3.5 Update 2.
 - Select discard data if you do not want to save your Sun Management Center 3.0 data.
- Select the production environment.
- Select the agent layer only

7. Set up the agent on machine C.

During agent setup:

- Provide a password to generate the security key.
The password must be the same password you provided when you set up the Sun Management Center 3.5 Update 2 server.
- Provide an SNMPv1 security string.
The security string must be the same security string you provided when you set up the Sun Management Center 3.5 Update 2 server.
- If you chose to migrate the Sun Management Center 3.0 agent data to Sun Management Center 3.5 Update 2, choose whether to restore the Sun Management Center 3.0 data.

When agent setup is finished, you are given the option to start the Sun Management Center agent. Start the agent.

8. Install the Sun Management Center 3.5 Update 2 console on machine A.

- a. Type the command `/opt/SUNWsymon/sbin/es-uninst` to uninstall the Sun Management Center 3.0 console.
- b. Install and set up the Sun Management Center 3.5 Update 2 console as described in [“Installing Sun Management Center” on page 29](#).

When the console setup is finished, start the console by typing the command `/opt/SUNWsymon/sbin/es-start -c`.

Sun Management Center 2.1.1 to Sun Management Center 3.5 Update 2 Upgrade

In this example, the Sun Management Center 2.1.1 server, agent, and console are installed on three machines as follows:

- The Sun Management Center 2.1.1 console is installed on machine A.
- The Sun Management Center 2.1.1 server is installed on machine B.
- The Sun Management Center 2.1.1 agent is installed on machine C.

The following procedure summarizes the steps required to upgrade the Sun Management Center 2.1.1 installation to Sun Management Center 3.6 on all three machines.

▼ To Upgrade From Sun Management Center 2.1.1 to Sun Management Center 3.5 Update 2

- Steps**
1. **Make sure each machine is a supported platform.**
See “Supported Platforms” on page 53.
 2. **Make sure each machine has the required resources.**
See “Preinstallation Checklist” on page 74.
 3. **Determine whether you will install Sun Management Center 3.5 Update 2 from the CDs or from a CD image.**
See “Determining the Installation Source” on page 85.
 4. **Upgrade the Sun Management Center 2.1.1 server on Machine B.**
 - a. **Make sure each machine has the required resources.**
See “Preinstallation Checklist” on page 74.
 - b. **Download the migration utility from <http://www.sun.com/sunmanagementcenter>.**
 - c. **Run the migration utility and upgrade from Sun Management Center 2.1.1 to Sun Management Center 3.5 Update 2.**
See “Upgrading From Sun Management Center 2.1 or 2.1.1” on page 93.

During the Sun Management Center 3.5 Update 2 installation stage of the upgrade process:

- Select the production environment.
- Select the server layer only. The agent is automatically installed.
- Choose whether to migrate the Sun Management Center 2.1.1 data.
 - Select migrate data to save your Sun Management Center 2.1.1 data and use the data in Sun Management Center 3.6.
 - Select discard data if you do not want to save your Sun Management Center 2.1.1 data.

During the Sun Management Center 3.5 Update 2 setup stage of the upgrade process:

- Provide a password to generate the security key.
The password must be the same for all Sun Management Center machines.
- Provide an SNMPv1 security string.
The security string must be the same for all Sun Management Center machines.

- If you chose to migrate the Sun Management Center 2.1.1 data to Sun Management Center 3.5 Update 2, choose whether to restore the Sun Management Center 2.1.1 data.

When server setup is finished, you are given the option to start the Sun Management Center components. Start all components.

5. Upgrade the Sun Management Center 2.1.1 agent on machine C.

Install the Sun Management Center 3.5 Update 2 agent on machine C as described in [“Installing Sun Management Center”](#) on page 29.

During agent installation:

- Select Migrate Data if you want to save your the Sun Management Center 2.1.1 agent data and use the data in Sun Management Center 3.5 Update 2.
- Select the production environment.
- Select the agent layer only

When the agent installation is finished, you are given the option to run setup. Run setup.

6. Set up the agent on machine C.

During agent setup:

- Provide the same security key password that you provided in [Step 4](#).
- Provide the same SNMPv1 community string that you provided in [Step 4](#).
- Provide the name of the Sun Management Center server machine.
- If you chose to migrate the Sun Management Center 2.1.1 agent data to Sun Management Center 3.5 Update 2, choose whether to restore the Sun Management Center 2.1.1 data.

Note – If you provide a different password for security seed generation on the server than you provided for Sun Management Center 3.0, then you must use the new password to generate the same security seed when setting up the agents. If you do not upgrade a Sun Management Center 3.0 agent to Sun Management Center 3.5 Update 2, you must regenerate the security key for the Sun Management Center 3.0 agent machine as described in [“Regenerating Security Keys”](#) on page 178.

When agent setup is finished, you are given the option to start the Sun Management Center agent. Start the agent.

7. Install the Sun Management Center 3.5 Update 2 console on machine A.

- a. Uninstall the Sun Management Center 2.1.1 console as described in the [Sun Management Center 2.1.1 Installation Guide](#).

- b. Install and set up the Sun Management Center 3.5 Update 2 console as described in [“Installing Sun Management Center” on page 29](#).

When console setup is finished, start the console by typing the command `/opt/SUNWsymon/sbin/es-start -c`.

Using Agent-Update to Upgrade Agents to Sun Management Center 3.6

In this example, the systems in the network have Sun Management Center 3.6 and Sun Management Center 3.0 installed as follows:

- The Sun Management Center 3.6 console and agent are installed on machine A.
- The Sun Management Center 3.6 server and agent is installed on machine B.
- The Sun Management Center 3.0 agent is installed on machines C through Z.

The following procedure summarizes the major steps required to upgrade machines C through Z to the Sun Management Center 3.6 agent.

▼ To Upgrade Agents to Sun Management Center 3.6 Using Agent-Update

- Steps**
1. Make sure that all Sun Management Center components on the Sun Management Center server machine B are running as described in [“Starting Components on the Solaris Platform” on page 166](#).
 2. Create an agent-update image as described in [“To Create an Agent-Update Image Using es-gui-imagetool” on page 103](#).
 3. Apply the agent-update image to machines C through Z as described in [“To Install or Update Agents From an Agent-Update Image Using agent-update.bin” on page 122](#).

While applying the agent-update image on each machine:

- Provide a password to generate the security key.
The password must be the same password you provided when you set up Sun Management Center 3.6 server.
- Provide an SNMPv1 security string.
The security string must be the same security string you provided when you set up Sun Management Center 3.6.

To Install the Sun Management Center Console on Microsoft Windows

If a previous Sun Management Center console version is installed on the Microsoft Windows machine, uninstall the console as described in “[Uninstalling Sun Management Center From the Microsoft Windows Platform](#)” on page 211.

To install the Sun Management Center 3.6 console, install the console as described in “[Installing Sun Management Center 3.6 on Microsoft Windows](#)” on page 153.

Product Documentation

The documentation for Sun Management Center 3.6 is *not* available on the software CD. The English documents and localized documents are available at <http://docs.sun.com>.

Configuration Considerations

This chapter discusses items that can adversely affect your Sun Management Center installation or upgrade. This chapter provides the following topics:

- “Security Recommendations” on page 65
- “Management Strategies” on page 69

Security Recommendations

This section provides security recommendations for Sun Management Center access, server and agent components, and security keys.

Users, Groups, and Roles Overview

Before you set up Sun Management Center users and user groups, you should understand the types of management operations that are possible so you can assign these operations to the appropriate user classes. Careful planning of user groups and roles helps ensure proper configuration management, and data integrity and security of management information and system resources.

No user may gain access to Sun Management Center without first being explicitly identified in the master access file `/var/opt/SUNWsymon/cfg/esusers`. To grant access to Sun Management Center, the user’s UNIX user name must be added to `/var/opt/SUNWsymon/cfg/esusers`. The user may then log into Sun Management Center using the standard UNIX user name and password.

When a user logs in, Sun Management Center controls access and defines the user privileges based on the following functional roles:

- **Domain Administrators** – This role is the highest-level role, which permits members to create top-level domains in a server context and to assign privileges for other Sun Management Center users within these domains. The domain administrator can create customized configurations for specific topology environments by creating specific domains and assigning user privileges for those domains. Users are considered domain administrators if the users are members of the `esdomadm` UNIX user group.
- **Administrators** – This role is the administration role for all operations outside the topology system. Administrators can perform privileged operations, including the loading of modules and the configuration of managed objects and data properties. Administrators can also specify access control at the agent and module level. This control makes this role instrumental in the establishment and maintenance of entitlement policies. Users are considered administrators if the users are members of the `esadm` UNIX user group.
- **Operators** – This role allows system users to configure their own domains and topology containers. The operator role also allows the users to configure managed objects with respect to their data acquisition and alarms, and to view management information. Although operators may enable or disable management modules, operators cannot, by default, load modules or alter access control privileges. Operators therefore represent a class of user that can effectively use the product and fine-tune its operation but who cannot affect major configuration or architectural changes. Users are considered operators if the users are members of the `esops` UNIX user group.
- **General Users** – This role is for users who are not explicitly members of the above three groups. General users are not granted extensive privileges and can by default only view management information and acknowledge alarms. The general user role is well suited for first-level support, in which problem identification, re-mediation, and escalation are the primary goals.

In large organizations, the Sun Management Center security roles are likely to map directly onto existing systems administration and support functions. For others, the process could be more involved, as the mapping between a corporate function and a product role could be less clear. In some cases, assignment of all logical roles to a single user could be warranted.

Note – Specification of privileges is flexible and does not need to be confined to the four Sun Management Center security roles.

Sun Management Center privileges can be explicitly specified at the domain, topology container, agent, and module levels. The privileges specification can reference any arbitrary UNIX user or group, with the groups named above being used only by convention. The Sun Management Center privileges groups allow the use of existing account configurations when assigning functional roles. Although naming explicit users when assigning privileges is not recommended, the use of UNIX groups can be convenient in environments where such UNIX groups are already established.

For further information on security roles, groups, and users, see “Setting Up Users” on page 157 and Chapter 18, “Sun Management Center Security,” in *Sun Management Center 3.6 User’s Guide*.

Sun Management Center Internal Security

This section describes the security process that is used between Sun Management Center components.

Server-to-Agent Security

Communication between the Sun Management Center server and its managed nodes is primarily performed using the industry standard Simple Network Management Protocol version 2, employing the User Security model SNMP v2sec. The SNMPv2 mechanism is well suited to mapping the user credentials from the server layer to agent-side operations. SNMPv2 is the primary mechanism for ensuring that access control policies cannot be circumvented.

Sun Management Center also supports SNMP v1 and v2 with community-based security. Although not as robust from a security standpoint, support for SNMP v1 and v2 is important for integration with other devices and other management platforms. In environments where the use of these mechanisms is undesirable, the access control specification mechanism can be used to restrict or forbid access to processes using the SNMP v1 and v2 protocols. The Sun Management Center agent can also understand and respond to SNMPv3 queries from third-party applications.

For customized operations where data streaming could be a requirement, a probe mechanism is also employed. The probe mechanism is initiated by SNMP operations. When initiated, probe operations use a streaming TCP connection to implement bidirectional, potentially interactive services on the managed node, for example, log file viewing. Since the probe mechanism uses SNMP communication, no encryption of the packet payload is performed.

Cross-Server Context Security

When Sun Management Center communicates with managed nodes outside the local server context, the security model ensures that operations are performed as the generic `espublic` SNMPv2 `usec` user. Use of `espublic` greatly restricts privileges and limits users to the perusal of management data.

Client-to-Server Security

Communication between the Sun Management Center server layer and clients such as consoles and command-line interfaces is performed using Java Technology Remote Method Invocation (RMI) in conjunction with a comprehensive product-specific security model. The security model allows clients to operate in either low, medium or high security modes, which affects the level of message authentication that is performed.

- **Low:** No message authentication. Only the user password is checked at time of login.
- **Medium (default):** Console-to-server authentication only, for example, server authentication of incoming console messages.
- **High:** Both console and server authenticate messages.

Because of the potential performance impact of the higher security levels, you should carefully consider your message authentication requirements.

Module Security

Sun Management Center provides module level security for *Service Management Facility (SMF)*, *Module Configuration Propagation (MCP)*, and *Solaris Container Manager* modules. Any user will be able to load any module on the Sun Management Center agent. However, for setting/changing actions or values on the module, the user needs to have prior permissions. Module security is provided in two ways: RBAC (Role Based Access Control) and local file access.

RBAC is based on profiles. Users having the required profiles can perform profile-specific tasks. RBAC can be implemented by running Solaris system administration commands.

Local file access is independent of the OS. The users need to have the required permissions to be added to the local access file. Security through local file access can be implemented by using the `es-config` command. For more information refer to [“Using es-config” on page 186](#).

Security Keys and SNMP Community String

When you install and then set up the Sun Management Center agent on a separate machine, you are prompted to provide a password that is used to generate the security key for the agent. The password should be the same password as the password you specified during setup of the Sun Management Center server. The Sun Management Center server and agent cannot communicate with each other if the server and agent have different security keys. For information on how to regenerate security keys, see [“Regenerating Security Keys” on page 178](#).

During setup, you are also prompted to either accept the default SNMP community string (public), or specify a private community string. The SNMP community string is essentially a password for a privileged internal account. As such, this string potentially can be used to mimic the server layer if used with generic SNMPv2 usec tools. Therefore, do not use the default community string. Specify a separate, private community string for each server context.

Treat the security password and the SNMP community string with the same significance as a superuser password.

Management Strategies

This section provides an overview of Sun Management Center management approaches. Understanding the systems under management and their implementation can contribute to the successful deployment and use of Sun Management Center.

Server Contexts

The highest-level building block for the organization of management information is the server context. Each Sun Management Center server provides only one server context. Each server context might have one or more managed systems that report to the server context. A managed system can report to only one server context.

Communication between server contexts is typically restricted, and management events are not forwarded between servers. The use of server contexts should parallel the structure of the groups within the organization using Sun Management Center. Server contexts should also parallel the responsibilities of these groups with respect to systems management. The administrative group that owns the server also owns the management data within the server. This group controls all access to all system and network resources managed by the Sun Management Center server.

Domain Strategies

Domains are the highest-level construct within a server context. Domains provide individual environments within which you can create custom topology configurations. Domains are very generic. You can create a domain to represent information specific to users, environments, or any other logical division. Managed systems may appear in more than one domain, enabling multiple, overlapping domains to exist. You can therefore construct several different representations of the same management information and system resources.

Domains typically contain a hierarchical collection of Sun Management Center groups that you can use to aggregate sets of managed systems, Sun Management Center management modules, or managed objects. This hierarchy defines the visible breakdown of information in the user interface. This hierarchy also defines the rules for aggregating management status and providing this status to high-level summaries. This capability and flexibility makes domains, and the containers within them, a powerful tool for the construction of logical management models of a specific environment.

Organization Strategies

Sun Management Center contains a powerful Discovery Manager, which can be used to automatically and periodically examine the local environment to identify all managed nodes. While instrumental in the configuration of Sun Management Center, the Discovery Manager structures management information along physical, network-based lines.

Depending on the nature of your environment, using the Discovery Manager might not be the most useful way to view management information and aggregate status information. Conversely, using the Discovery Manager is very useful for identifying all managed systems prior to organizing your Sun Management Center environment. For further information about the Discovery Manager, see Chapter 4, “Adding Objects to the Topology Database Using the Discovery Manager,” in *Sun Management Center 3.6 User’s Guide*.

Other ways to organize the Sun Management Center environment include:

- Physical
- Environmental
- Application
- Service

In each of the Sun Management Center environments, emphasis should be placed on completeness. The breadth of coverage must be sufficient to pro-actively or at least immediately identify system problems. Failures in devices, hosts, services, or processes that are critical to an environment but that are not being monitored by Sun Management Center can cause gaps in the coverage that will affect the overall effectiveness of an implementation. To this end, you should consider customized modules, proxy solutions, and even information from other server contexts when building your Sun Management Center management environments.

Physical Organization

The physical locations of managed systems might not correspond to the networks on which the systems reside. In this case, you might want to create a new domain in which the Sun Management Center groups are structured on physical lines. Cities,

sites, buildings, floors, server rooms and even equipment racks can easily be represented. The systems at these locations can be copied and pasted from the domain in which discovery was performed using the Discovery Manager.

To configure a Sun Management Center environment along physical lines requires you to know where the systems are physically located. This organization can become a valuable and easily accessed reference. A physical organization also defines a status roll-up path, enabling problems to be isolated on physical lines and assisting in the identification of common-mode failures. For example, a localized power outage might affect systems that reside on several networks but will only appear in one physical area.



Caution – You must keep the information up-to-date yourself. This information is not automatically updated when discoveries are performed. The discovery process does not automatically track assets that are physically relocated.

Environmental Strategies

Your organization might have several logical environments whose locations and resources overlap, but whose logical functions are distinct. Logical environments include corporate groups such as sales versus engineering, functional groups such as retail versus institutional, and even logical software environments such as user acceptance versus production.

In all of these cases, consider producing separate Sun Management Center topology groups that isolate the elements of each group. Separate topology groups prevent problems in one group from raising alarms in another group. This isolation is particularly important when configuring the Sun Management Center environment for systems that include multi-domain servers. The different domains might be performing functions for completely different groups or environments. The inclusion of the different domains in a single topology group could result in misleading information and alarm notifications.

Application Organization

Applications are complex entities in systems management. Determining what constitutes an application from a management perspective can be difficult, particularly when applications are distributed and rely on many external services to operate properly. For this reason, you should organize applications before installing Sun Management Center. Do not defer consideration of the cause and effect relationships until a problem is actually encountered. Some initial analysis contributes to increasing the efficiency with which application-level problems are resolved.

When configuring an application-oriented Sun Management Center environment, the topology containers typically contain a mix of hosts, modules, and specific objects. Some hosts might be completely dedicated to that application, while other hosts might

only be partially responsible for the application's proper operation. For example, in the case of an application that makes use of a corporate directory service, the health of the directory service is critical to the operation of the application, but the health of other services on the server are not critical to or needed by the application.

Services Responsibilities

In some circumstances, a group or administrator might be responsible for a specific service but not the underlying resources. For example, a database administrator might be responsible for the database service availability and data integrity, but not responsible for the hardware or operating system administration. A Sun Management Center domain that is created specifically for the database services can assist the database administrator in performing the necessary tasks. General user role privileges can assist the administrator by providing access to general system and network status.

Managing Large Enterprises

Several facilities in Sun Management Center can help you to simplify management of large enterprises. One facility is Reference Domains, which allow groups to share management information across server contexts. Another feature is the Grouping Operations system, which facilitates performing large, highly distributed management operations.

The grouping system enables you to set data property values, and modify data property attributes. You can also load, unload, enable, and disable modules in your Sun Management Center server environment. All of these operations can be applied to a large group of managed systems and nodes. These groups can be defined using existing topology structures or flexible, discovery-style filters. Grouping operations can be saved and performed multiple times. A scheduler is available to automate grouping operations. Grouping operations also include Module Configuration Propagation (MCP), a facility in which a reference node's entire configuration can be cloned by pulling it to the server and then pushing it to all similar nodes.

For further information about Reference Domains, see "Monitoring Remote Administrative Domains" in *Sun Management Center 3.6 User's Guide*. For further information about group operations, see Chapter 13, "Managing Group-related Jobs," in *Sun Management Center 3.6 User's Guide*.

Preparing Systems for Sun Management Center Upgrade and Installation

This chapter provides procedures for preparing your Solaris and Microsoft Windows systems for Sun Management Center 3.6 installation.

This chapter discusses the following topics:

- [“Compatibility With Other Software and Earlier Versions of the Product”](#) on page 73
- [“Preinstallation Checklist”](#) on page 74
- [“Prerequisite Packages”](#) on page 76
- [“Solaris Systems With More Than 4 Gbytes RAM”](#) on page 76
- [“Java Environment Variables and Path”](#) on page 77
- [“Microsoft Windows 98 Swap Space and Environment Space”](#) on page 79
- [“Sun StorEdge A5x00 Packages”](#) on page 81
- [“T3 Storage Devices”](#) on page 81
- [“Determining the Installation Source”](#) on page 85

Compatibility With Other Software and Earlier Versions of the Product

Sun Management Center 3.6 software is compatible with the following software:

- Any Simple Network Management Protocol (SNMP) v1, v2, v2 usec, and v3 entities, regardless of the operating environment and architecture.
- Solstice Enterprise Agents™ software for Solaris 2.6, Solaris 7, Solaris 8, Solaris 9, and Solaris 10 operating environment versions. Solstice agents can coexist with Sun Management Center agents on the same host system if you configure the Solstice agents as subagents of the Sun Management Center agent. See [“Configuring a Legacy SNMP Agent as a Subagent of an Agent”](#) on page 181.

Sun Management Center software does *not* offer the following features:

- Backward compatibility with the Solstice SyMON™ 1.x software
- SunVTS™ support in the Sun Management Center 3.6 software

The following table lists prior Sun Management Center version compatibility by Sun Management Center base product layer. Sun Management Center versions 2.0 and 2.0.1 are referred to as Sun Enterprise SyMON™ software. Versions 2.1, 2.1.1, 3.0, and 3.6 are referred to as Sun Management Center.

TABLE 4-1 Sun Management Center Prior Version Compatibility by Base Product

ConsoleServer	Agent	
3.0	3.0	2.0.1, 2.1, 2.1.1, 3.0
3.5	3.5	2.0.1, 2.1, 2.1.1, 3.0, 3.5
3.6	3.6	2.0.1, 2.1, 2.1.1, 3.0, 3.5, 3.6

Preinstallation Checklist

The following list describes the tasks that you need to perform before you can install Sun Management Center 3.6, or upgrade an existing SyMON or Sun Management Center installation to Sun Management Center 3.6.

- If the Solstice SyMON server, or the Enterprise SyMON server is installed, you must upgrade the SyMON installation to Sun Management Center 2.1 or Sun Management Center 2.1.1 before you can upgrade to Sun Management Center 3.6. See [“Upgrading from Solstice SyMON 1.x and Sun Enterprise SyMON 2.x Software” on page 92.](#)

If you customized the `email.sh` script that Sun Enterprise SyMON software uses to send email notification of alarm conditions, save the `email.sh` script to another directory, then move the script back after your upgrade is complete. The `email.sh` script is overwritten when you upgrade SyMON software to version Sun Management Center 3.6.

Note – If you do not want to migrate your SyMON configuration data, you must uninstall the SyMON software as described in [“Uninstalling Solstice SyMON 1.x or Enterprise SyMON 2.x” on page 206](#) before you can install Sun Management Center 3.6.

- Determine which components of Sun Management Center 3.6 and which product add-ons you want to install on each machine on your network.
 - Make sure the platforms on which you want to install Sun Management Center or Sun Management Center components are supported platforms. See [“Supported Platforms” on page 53.](#)

- For minimum RAM and disk space requirements, see [Chapter 1](#). Also, refer to the Sun Management Center add-on product supplements at <http://docs.sun.com>.
Total the amount of RAM and disk space needed for the selected components and add-on products.
- Ensure that each machine is running the correct operating system for the components you want to install. See [Table 1-3](#) and [Table 1-4](#).
- Ensure that the correct JDK version is installed on machines that are designated for the Sun Management Center server and console components. See [Table 1-3](#). You can download the JDK software from <http://java.sun.com/>.
- Set the `PATH` and the `JAVA_HOME` environment variables.
 - For the Solaris platform:
Make sure that the `DISPLAY` and `JAVA_HOME` environment variables are set in any account that is used to run the Sun Management Center Web or Java console.
The default location for JDK versions 1.3.1 and 1.4 is `/usr/j2se`. See [“To Set JAVA_HOME and PATH on the Solaris Platform”](#) on page 77.
 - For the Microsoft Windows platform:
Ensure the path to the JDK `bin` directory is added to the Microsoft Windows `%PATH%` environment variable. See [“To Set PATH on Microsoft Windows 98”](#) on page 77.
- If any machine on your network has 4 Gbytes of RAM or more, install the 64-bit compatibility patch `SUNWscpux` on the machine. See [“Solaris Systems With More Than 4 Gbytes RAM”](#) on page 76.
- If your network includes StorEdge A5X00 devices, install the required patches. See [“Sun StorEdge A5x00 Packages”](#) on page 81.
- If your network includes T3 storage devices, you must update the `/etc/hosts` and `/etc/ethers` files on the machine to which the devices are attached. You must also update the `/etc/hosts` and `/etc/ethers` files on the machine where you will install the Monitoring and Management of A5X00 and T3 Devices add-on product. See [“T3 Storage Devices”](#) on page 81.
- If you are upgrading an older version of Sun Management Center and you use the older version to monitor and manage T3 devices, you must remove Sun Management Center T3 device configuration before performing the upgrade to Sun Management Center 3.6. See [“Removing T3 Device Configuration If Present”](#) on page 83.
- Select the installation source.
You can install from a CD-ROM disk or from CD images. See [“Determining the Installation Source”](#) on page 85.

Prerequisite Packages

The following Solaris operating environment packages are required by the Sun Management Center 3.6 server layer, and are included as part of the Solaris development environment installation.

- SUNWsprot - Solaris Bundled tools
- SUNWt00 - Programming Tools
- SUNWbtool - CCS tools included with SunOS

Solaris Systems With More Than 4 Gbytes RAM

The SUNWscpx 64-bit source compatibility package must be installed on systems that have more than 4 Gbytes of RAM before you can install Sun Management Center 3.6. If the package is not installed, the command-line installation process will report the following messages and fail.

```
ps: read() on /proc/551/as: Value too large for defined data type
ps: read() on /proc/542/as: Value too large for defined data type
```

The SUNWscpx package is installed automatically during Solaris installation when any of the following Solaris environments are selected.

- Entire +OEM
- Entire
- Developer

To determine if the package is installed on the system, type the command `pkginfo SUNWscpx` in a terminal window.

- If the package is installed, information about the package is displayed.

```
# pkginfo SUNWscpx
system      SUNWscpx      Source Compatibility (Usr) (64-bit)
```

- If the package is not installed, an error message is displayed.

```
# pkginfo SUNWscpx
ERROR: information for "SUNWscpx" was not found
```

To install the SUNWscpx package:

1. Log in as root (`su - root`).
2. Locate the package on the Solaris installation CD.

3. Install the package using the `pkgadd` command.

Java Environment Variables and Path

The `JAVA_HOME` and `PATH` environment variable must be set on Solaris systems in order for the Sun Management Center 3.6 installation wizards, the setup wizards and the Java console to function properly. Similarly, the Microsoft Windows `%PATH%` must be modified to include the path to the JDK software for the Sun Management Center Java console to work properly on Microsoft Windows.

If the environment variables and path are not set properly, installation and setup of Sun Management Center 3.6 can fail.

▼ To Set `JAVA_HOME` and `PATH` on the Solaris Platform

If JDK 1.3.1 or JDK 1.4 software has been installed in the default location:

- Steps**
1. Log in as root by typing `su - root`.
 2. Set `JAVA_HOME` to `/usr/j2se`.

- In a C shell environment:

```
# setenv JAVA_HOME /usr/j2se
```

- In a Bourne or Korn shell environment:

```
# JAVA_HOME=/usr/j2se
# export JAVA_HOME
```

Tip – Add the appropriate statement to your `.login` or `.cshrc` file.

3. Add `/usr/j2se/bin` to your system path.
4. Place `/usr/j2se/bin` in your `PATH` before `/usr/bin`.
5. Place `/usr/bin` in your `PATH` before `/usr/ucb`.

▼ To Set `PATH` on Microsoft Windows 98

The following procedure assumes that JDK 1.3.1 or JDK 1.4 software has been installed to the default location `C:\j2sdk<version number>`, for example, `C:\j2sdk1.4`.

Steps 1. Edit the file `c:\autoexec.bat`.

2. Add the location of the JDK bin directory to the `PATH` statement.

For example, if the `PATH` statement in the `autoexec.bat` file is `PATH=c:\windows;c:\windows\command`, the new `PATH` statement would then be `PATH=c:\windows;c:\windows\command;c:\j2version-number\bin` where *version-number* is the JDK version.

For example:

```
PATH=c:\windows;c:\windows\command;C:\j2sdk1.4\bin
```

Separate each directory in the `PATH` statement with a semicolon as shown.

3. Save and close the file.

▼ To Set `PATH` on Microsoft Windows NT or Microsoft Windows 2000

Steps 1. Choose **Start** → **Settings** → **Control Panel**.

2. Double-click **System**.

3. On Microsoft Windows NT, select the **Environment** tab. On Microsoft Windows 2000, select the **Advanced** tab and then **Environment Variables**.

The Environment Variables window is displayed.

4. Click **Path** in the **User Variables and System Variables**.

5. Click **Edit**.

The Edit System Variable window is displayed.

Note – The Edit System Variable window shows the Microsoft Windows root directory using the environment variable `%SystemRoot%`.

6. Add the location of the JDK bin directory to the `PATH` statement.

For example, if the `PATH` statement shown in the Edit System Variable window is `%SystemRoot%\system32;%SystemRoot%`, the new path statement would then be `%SystemRoot%\system32;%SystemRoot%;c:\j2version-number\bin` where *version-number* is the JDK version.

For example:

```
%SystemRoot%\system32;%SystemRoot%;c:\j2sdk1.4\bin
```

Separate each directory in the `PATH` statement with a semicolon as shown.

7. Click OK to successively close each window.

▼ To Set `PATH` on Linux

- Steps**
1. Change to your home directory.

```
cd $HOME
```

2. Open the `.bashrc` file.

3. Add the following line to the file. Replace the *JDK directory* with the name of your java installation directory.

```
export PATH=/usr/java/<JDK Directory>/bin:$PATH
```

4. Save the file and exit.

Use the `source` command to force Linux to reload the `.bashrc` file which normally is read only when you log in each time.

```
source .bashrc
```

Note – Note that if you wish to set the `PATH` for all users, you need to log in as root in the bash shell and perform the above steps on the `.profile` file in the `etc` directory and not the `.bashrc` file in the home directory.

Microsoft Windows 98 Swap Space and Environment Space

Microsoft Windows 98 requires a minimum of 768 Mbytes of swap space or *virtual memory* to run the Sun Management Center 3.6 console. 4096 bytes of environment space are required for the Microsoft Windows 98 and the Sun Management Center environment variables. If the swap space and environment space are not set correctly, Sun Management Center installation could fail and your machine could run out of environment space. Set the minimum swap space and environment space for Microsoft Windows 98 as described in the following procedures.

Note – The following procedures are applicable only to Microsoft Windows 98. Microsoft Windows NT and Microsoft Windows 2000 do not require you to set minimum swap space and environment space.

▼ To Set Microsoft Windows 98 Minimum Swap Space Size

- Steps**
- 1. Log in as administrator, or as the user account that has full administration privileges.**
 - 2. Choose Start → Settings → Control Panel.**
 - 3. Double-click the System icon.**
The System Properties window appears.
 - 4. Select the Performance tab.**
The Performance Options window is displayed.
 - 5. Select Virtual Memory.**
 - 6. Select Let me specify my own virtual memory settings.**
 - 7. Type 768 in the Minimum field.**
The value in the Maximum field must be at least three times the amount of total system RAM.

For example, if your Microsoft Windows 98 machine has 512 Mbytes of RAM, the Maximum field value should be 1536.
 - 8. Click OK.**
The Confirm Virtual Memory Settings dialog box appears.
 - 9. Click Yes in the Confirm Virtual Memory Settings dialog box.**
The dialog box closes.
 - 10. Click Close in the System Properties window.**
The System Properties window closes, and you are prompted to reboot the system.
 - 11. Click Yes to reboot the system.**
The virtual memory settings that you specified are applied and used when the system completes rebooting.

▼ To Set Microsoft Windows 98 Minimum Environment Space Size

Steps 1. Add the following line to the `config.sys` file if the line is not present.

```
SHELL=C:\COMMAND.COM /P /E:4096
```

2. If you added the `shell` line to the `config.sys` file, or if you modified the existing `shell` line, reboot the system.

Sun StorEdge A5x00 Packages

If you want to use the Sun StorEdge A5x00 module, you must install either the `SUNWluxop` or the `SUNWluxox` packages on the system where you install the Monitoring and Management of A5x00 and T3 Devices add-on product. If you load the A5x00 module and the packages are not installed on the system, the Sun Management Center agent cannot run. .

To check whether the packages are installed, type the following command:

```
# pkginfo SUNWluxop SUNWluxox
```

If the packages are installed, the following lines are displayed:

```
system SUNWluxop Sun Enterprise Network Array firmware and utilities
system SUNWluxox Sun Enterprise Network Array libraries (64-bit)
```

If you need either package, you can download the package from <http://sunsolve.sun.com>. Make sure that you download the latest revision. Use the `pkgadd(1M)` command to install the packages.

T3 Storage Devices

This section provides the procedures for preparing T3 devices for Sun Management Center 3.6, and procedures for removing T3 device configuration data from existing Sun Management Center 2.x or Sun Management Center 3.x installations.

Note – T3 device configuration data must be removed from existing Sun Management Center installations before you can upgrade to Sun Management Center 3.6.

Preparing a T3 Storage Device

Before you install and set up the Sun Management Center T3 Add-on, you must modify the `/etc/hosts` and `/etc/ethers` files on the system where the Sun Management Center add-on Monitoring and Management of A5X00 and T3 Devices is to be installed.

The following procedure assumes that you have installed and configured the T3 storage device as described by the *Sun StorEdge T3 Disk Tray Installation, Operation, and Service Manual*.

When the `/etc/hosts` and `/etc/ethers` files have been updated on the machine where the Sun Management Center add-on Monitoring and Management of A5X00 and T3 Devices will be installed, you can proceed with installing and setting up the T3 add-on.

▼ To Prepare a T3 Storage Device

Steps 1. **Determine the IP address and Ethernet address for each T3 storage device.**

Open a terminal window and type the command `arp t3-device-name` where `t3-device-name` is the name of the T3 storage device. For example:

```
# arp T3-001
T3-001 (10.100.20.300) at 1:2:30:ab:ba:45 permanent published
```

In the above example, `10.100.20.300` is the IP address, and `1:2:30:ab:ba:45` is the Ethernet address of the T3 storage device T3-001.

2. **Repeat Step 1 for each T3 device on your network.**

When you have recorded the IP address, Ethernet address, and name for each T3, go to the next step.

3. **Log in as root on the machine where you will install the Sun Management Center add-on Monitoring and Management of A5X00 and T3 Devices.**

This machine can be either the machine where you install the Sun Management Center server or the machine that you have allocated as dedicated platform agent server.

4. **Record each T3 IP address and name in the `/etc/hosts` file.**

For example, assume that three T3 devices are attached to your network. Assume that you used the `arp` command to determine the IP address, and Ethernet address

of each T3 device, and recorded the information as follows:

storage-t3-1	172.16.100.10	0:20:f2:0:59:48
storage-t3-2	172.16.100.11	0:20:f2:0:5f:40
storage-t3-3	172.16.100.12	0:20:f2:0:7f:a8

The entries in the server `/etc/hosts` file would then be as follows:

```
172.16.100.10 storage-t3-1
172.16.100.11 storage-t3-2
172.16.100.12 storage-t3-3
```

5. Record each T3 storage device Ethernet address and name in the `/etc/ethers` file.

Create the `/etc/ethers` file if the file does not already exist.

Using the example given in [Step 4](#), the entries in the server `/etc/ethers` file would then be as follows:

```
0:20:f2:0:59:48 storage-t3-1
0:20:f2:0:5f:40 storage-t3-2
0:20:f2:0:7f:a8 storage-t3-3
```



Caution – If you include the domain name as part of the T3 device name, make sure the domain name is identical in both the `/etc/hosts` and `/etc/ethers` files. The entries are case sensitive.

For example, assume that the `/etc/hosts` file contains:

```
0:20:f2:0:59:48 storage-t3-1.sun.com
```

Also assume that the `/etc/ethers` files contains

```
0:20:f2:0:59:48 storage-t3-1.Sun.Com
```

In this example, the T3 storage device cannot be set up using the Sun Management Center setup tools because the domain name case is different.

Removing T3 Device Configuration If Present

Uninstalling T3 Storage Devices

If you are running Sun Management Center, you must remove the T3 device configuration from Sun Management Center if you are going to perform any of the following functions:

- Remove the T3 storage device
- Move the T3 storage device to another machine
- Assign a different IP or Ethernet address to the T3 storage device
- Migrate the Sun Management Center server to a different machine
- Uninstall the Monitoring and Management of A5x00 and T3 Devices add-on product
- Uninstall Sun Management Center

Note – If you uninstall the Monitoring and Management of A5x00 and T3 Devices add-on product without first removing the T3 device configuration, you can remove the T3 device configuration as described in the following procedure.

The corrected procedure is as follows:

▼ To Remove T3 Device Configuration

- Steps**
1. Log in as **root** on the machine where the Monitoring and Management of A5x00 and T3 Devices add-on product is installed.
 2. Type the following command to stop the Sun Management Center agent.

```
#/opt/SUNWsymon/es-stop -a
```
 3. Run the **pre-uninstall** script to remove T3 device configuration information.
 - a. Type the command

```
/opt/SUNWsymon/addons/storage/sbin/pre-uninst.sh.
```
 - b. When asked whether you want to stop the T3 from sending syslog messages, type **y**.
You are then prompted for the root password for the T3 device.
 - c. Type the password.
You are notified that the T3 device has been removed from the T3 module.
 4. Uninstall the add-on product.

Determining the Installation Source

You can install, set up, and configure Sun Management Center 3.6 using either the Sun Management Center installation CDs or a Sun Management Center installation image located on your network. CD images eliminate the need to install Sun Management Center on each machine from the CDs.

This section provides the procedures for creating Sun Management Center installation images.

- [“Creating Installation CD Images” on page 85](#)
- [“Creating CD Images From the Download Tar File” on page 87](#)

There are two methods for capturing an installation image. You can copy Sun Management Center installation CDs to a location on your network. You can also download and unpack the Sun Management Center installation image from the Sun Management Center Web site.

Note – To install, set up, and configure , you must be logged in as root on Solaris machines, and as administrator on Microsoft Windows.

Creating Installation CD Images

To create the Sun Management Center CD images, you create a directory to contain the images, copy each CD to the directory, and then share the directory using network file system mounting.

▼ To Create CD Images

Steps 1. In a terminal window, log in as root by typing `su - root`.

2. Create a directory to which you will copy each CD.

For example:

```
# mkdir /SunManagementCenter
```

3. Change to the directory you created for the CD images.

For example:

```
# cd /SunManagementCenter
```

4. Create a `diskn` directory for each CD, where *n* is the sequence number of the disk.

For example:

```
/SunManagementCenter# mkdir disk1 disk2
```

5. Make sure the `vold` daemon is running.

```
/SunManagementCenter# ps -eaf | grep vold
root 19033 19000 0 08:37:55 pts/9 0:00 vold
/SunManagementCenter#
```

If the `grep` command returns only the system prompt, then the `vold` daemon is not running, and must be started as follows:

```
/SunManagementCenter# /usr/sbin/vold &
```

6. Insert Sun Management Center 3.6 CD 1 of 2 in your CD-ROM drive.

7. List the contents of the Sun Management Center 3.6 installation CD 1. Then copy the contents to the `disk1` subdirectory.

When the copy completes, list the contents of the CD and the directory to verify the contents of the disk image.

For example:

```
/SunManagementCenter# cp -r /<DiskMountDir>/.* disk1
/sunmanagementcenter > ls -acp /<DiskMountDir>/.*
.          .CD          Copyright  image/      lib/
..         .CD01        classes/   install/    sbin/
/sunmanagementcenter > ls -acp disk1
.          .CD          Copyright  image/      lib/
..         .CD01        classes/   install/    sbin/
```



Caution – `<DiskMountDir>` is a symbolic link. Copy *only* the Sun Management Center directory as shown in the above example.

8. Eject CD 1 of 2.

```
SunManagementCenter# eject
```

9. Insert Sun Management Center 3.6 CD 2 of 2 in your CD-ROM drive.

10. List the contents of the Sun Management Center 3.6 installation CD 2. Then copy the contents to the `disk2` subdirectory.

When the copy completes, list the contents of the CD and the directory to verify the contents of the disk image.

For example:

```
/SunManagementCenter# cp -r /<DiskMountDir>/.* disk2
/sunmanagementcenter > ls -acp /<DiskMountDir>/.*
```

```

.          ..          .CD          .CD01          .CD02          Copyright image/
/sunmanagementcenter > ls -acp disk2
.          ..          .CD          .CD01          .CD02          Copyright image/

```

11. Eject CD 2 of 2.

12. Make the Sun Management Center 3.6 CD image directory NFS-shared.

Using NFS to share the CD image directory enables you to install Sun Management Center 3.6 from other machines by using the CD installation images instead of manually installing from the CDs.

a. Stop the Network File System daemon mountd:

```
/SunManagementCenter# /etc/init.d/nfs.server stop
```

b. Add the following line to the `/etc/dfs/dfstab` file.

```
share -F nfs -o ro cd-image-dir
```

where *cd-image-dir* is the Sun Management Center 3.6 cd-image directory that you created in [“Java Environment Variables and Path” on page 77](#).

For example: **share -F nfs -o ro /SunManagementCenter**

c. Save and close `/etc/dfs/dfstab`.

d. Start the Network File System daemon mountd:

```
/SunManagementCenter# /etc/init.d/nfs.server start
```

The Sun Management Center 3.6 cd-image directory is now accessible from other machines.

You can now use the Sun Management Center CD images to install Sun Management Center 3.6, or to upgrade previous versions of Sun Management Center as described in the following chapters.

Creating CD Images From the Download Tar File

You can download the Sun Management Center Sun Management Center compressed tar file from the Web to a Solaris machine on your network. You then decompress and untar the tar file to a cd-image directory.

To download Sun Management Center, you must be registered with Sun as a Sun Web site user, and log in using your registered user ID. The download software Web page provides a link for registration.



Caution – Before you download the tar file, ensure that you have at least 1.6 Gigabytes of free disk space for the tar file and for the CD image files that are created when you uncompress and unpack the tar file.

▼ To Download the Tar File From the Web Site

Steps 1. In a terminal window, log in as root on the system where you want to create the Sun Management Center installation image.

2. Go to the Sun Management Center Web site at <http://www.sun.com/sunmanagementcenter/>.

3. Click Get the Software.

4. Click Sun Management Center 3.6.

Follow the instructions and download the Sun Management Center 3.6 tar file to a location that is accessible by root.

5. Go to the location where the tar file has been downloaded:

```
# cd /download-directory
```

6. Extract the Sun Management Center packages:

```
# zcat downloaded-filename | tar xvf -
```

The cd-image source directory is created, containing the subdirectories `disk1` and `disk2`.

7. Make the Sun Management Center 3.6 cd-image directory NFS-shared.

Using NFS to share the CD image directory enables you to install Sun Management Center 3.6 from other machines by using the CD installation images instead of manually installing from the CDs.

For example, if you extracted the cd-images to the directory *SunManagementCenter*, you would make the directory NFS-shared as follows.

a. Stop the Network File System daemon mountd:

```
/SunManagementCenter# /etc/init.d/nfs.server stop
```

b. Edit the `/etc/dfs/dfstab` file.

Add the following line:

```
share -F nfs -o ro cd-image-dir
```

where *cd-image-dir* is the Sun Management Center 3.6 cd-image directory.

For example: `share -F nfs -o ro /SunManagementCenter`

c. Save and close `/etc/dfs/dfstab`.

d. Start the Network File System daemon mountd:

```
/SunManagementCenter# /etc/init.d/nfs.server start
```

The Sun Management Center 3.6 cd-image directory is now accessible from other machines.

You can now use the Sun Management Center CD images to install Sun Management Center 3.6, or to upgrade previous versions of Sun Management Center as described in the following chapters.

Upgrading Previous Versions of SyMON and Sun Management Center on the Solaris Platform

This chapter describes how to upgrade Solstice SyMON 1.x, Sun Enterprise SyMON 2.x, Sun Management Center 2.x, and Sun Management Center 3.0 software to Sun Management Center 3.6 on a single machine.

This chapter discusses the following topics:

- “Upgrade Considerations” on page 91
- “Upgrading from Solstice SyMON 1.x and Sun Enterprise SyMON 2.x Software” on page 92
- “Upgrading From Sun Management Center 2.1 or 2.1.1” on page 93
- “Upgrading From Sun Management Center 3.0” on page 95
- “Upgrade from 3.5 to 3.5 Update 1 or Update 2” on page 97
- “Upgrade from 3.5 Update 1 or Update 2 to 3.6” on page 98

Note – If you do not want to migrate your SyMON or Sun Management Center data, you must uninstall the existing SyMON or Sun Management Center software before you can install Sun Management Center 3.6. To uninstall existing SyMON or Sun Management Center software without saving your data, see [Appendix A](#)

Upgrade Considerations

When upgrading from any version of Sun Enterprise SyMON software, or upgrading from any version of Sun Management Center software, the server and console layers must be upgraded first.

As shown in [Table 4–1](#), Sun Management Center 3.6 servers and consoles support previous versions of Sun Management Center agents and Sun Enterprise SyMON 2.0.1 agents. Consequently, Sun Management Center agents can be upgraded when time or circumstances permit.

All Sun Management Center software components should be upgraded to version 3.6 to take advantage of the improved monitoring and management capabilities provided by Sun Management Center 3.6.

Note – When upgrading, make sure you use the same port number for the agent as you used in the previous installation. This advice is applicable to both an agent upgrade and a server upgrade.

Upgrading from Solstice SyMON 1.x and Sun Enterprise SyMON 2.x Software

If you are upgrading from Sun Enterprise SyMON 1.x or Sun Enterprise SyMON 2.x, you must first upgrade to Sun Management Center 2.1 or Sun Management Center 2.1.1 before you can upgrade to Sun Management Center 3.6. For upgrade procedures, see *Upgrading from Sun Enterprise SyMON 2.x to Sun Management Center 2.1 Software* in the *Sun Management Center 2.1 Software User's Guide*.



Caution – If you have modified SyMON 1.x or 2.x rules, back up the rules before you install Sun Management Center 3.6. The 3.6 installation and setup process could overwrite your SyMON 1.x or 2.x files. Depending on where you modified your event rules, back up the `/etc/opt/SUNWsymon` directory, the `/opt/SUNWsymon/etc` directory, or both directories.

When you have completed the upgrade to Sun Management Center 2.1 or Sun Management Center 2.1.1, follow the procedures in [“Upgrading From Sun Management Center 2.1 or 2.1.1”](#) on page 93 to upgrade to Sun Management Center 3.6.

The coexistence of the Solstice SyMON 1.x or Sun Enterprise SyMON 2.x software with Sun Management Center 3.6 software is not supported on the same server. In addition, you may have Sun Management Center sessions running on different servers or server contexts. For more information on server context, see “Sun Management Center Architecture” in *Sun Management Center 3.6 User's Guide*.

Upgrading From Sun Management Center 2.1 or 2.1.1

If you want to migrate your Sun Management Center 2.x server data and use it with Sun Management Center 3.6, use the migration utility as described below.

If you do not want to migrate your Sun Management Center 2.x server data, you must uninstall Sun Management Center 2.x before you can install Sun Management Center 3.6. To uninstall Sun Management Center 2.x, follow the procedures in “Uninstalling Sun Management Center 2.x” on page 206.

Note – If you want to migrate or upgrade your Sun Management Center 2.x agent to Sun Management Center 3.6, you do not need to run the migration utility. For agent upgrade procedures, see “Creating Agent Installation and Update Images” on page 101 and “Applying Agent Installation, Update, and Patch-Only Images” on page 121.

▼ To Upgrade From a Sun Management Center 2.x Server

- Steps**
1. Log in as root on the machine where the Sun Management Center 2.x server is installed.
 2. Prepare the system for Sun Management Center 3.6 as described in [Chapter 4](#).
 3. Download the tar file `sunmc_2x_server_upgrade.tar` from <http://www.sun.com/sunmanagementcenter/>.
 - a. Uncompress the tar file:

```
# tar xvf sunmc_2x_server_upgrade.tar
```
 - b. Read and follow the migration instructions in the file `sunmc_2x_server_upgrade_README.txt`.

The migration utility saves your Sun Management Center 2.x data in the directory `/var/opt/SUNWsymon/2x`.
 4. Uninstall the Sun Management Center 2.x software.

Type the command `/opt/SUNWsymon/sbin/es-uninst` and press Return.



Caution – Do not delete the Sun Management Center 2.x directories. The Sun Management Center 2.x uninstall process removes the Sun Management Center 2.x software, but does not remove the Sun Management Center 2.x data.

5. Upgrade the Solaris operating environment if necessary.

If you are upgrading the Sun Management Center 2.x server, the machine must be running either the Solaris version 8 or Solaris version 9 developer environment. For additional information, see [“Prerequisite Packages” on page 76](#)



Caution – If you need to upgrade to Solaris version 8 or Solaris version 9, make sure you perform a Solaris upgrade. A fresh Solaris installation reformats the hard drive, which deletes your Sun Management Center 2.x configuration data. If you perform a fresh Solaris installation, you will not be able to migrate your Sun Management Center 2.x configuration data to Sun Management Center 3.6.

- a. **Back up the `/var/opt/SUNWsymon/2x` directory and subdirectories to a different machine or backup device.**
- b. **Upgrade the Solaris operating environment.**
Refer to your Solaris documentation for procedures.
- c. **If necessary, restore the `/var/opt/SUNWsymon/2x` directory and subdirectories to the machine.**

6. Install Sun Management Center 3.6.

Use either the Sun Management Center 3.6 graphical user interface command `es-guiinst` or the command-line script `es-inst` to install Sun Management Center 3.6.

You will be notified that the exported Sun Management Center 2.x data has been detected, and that the data will be migrated to the new release.

- To upgrade Sun Management Center 3.6 using `es-guiinst`, see [“Installing Sun Management Center” on page 29](#).
- To upgrade Sun Management Center 3.6 using `es-inst`, see [“Installing Sun Management Center Using `es-inst`” on page 217](#).

Upgrading From Sun Management Center 3.0

As described in the following sections, Sun Management Center 3.6 provides several methods for upgrading the Sun Management Center 3.0 server and agent.

Upgrading the Server

You can upgrade the Sun Management Center 3.0 server to the Sun Management Center 3.6 using any of the following methods.

- Run the Sun Management Center 3.6 graphical user interface installation command `es-guiinst`.
- Run the Sun Management Center 3.6 command-line installation script `es-inst`.
- Uninstall Sun Management Center 3.0 and save the configuration data, then run either the Sun Management Center 3.6 `es-guiinst` command or the `es-inst` command.

The Sun Management Center 3.6 installation process detects the existing 3.0 installation and runs the Sun Management Center 3.0 `es-uninst` command-line script. The Sun Management Center `es-uninst` script gives you the option to save your Sun Management Center 3.0 data.

After you have installed Sun Management Center 3.6, if you saved your Sun Management Center 3.0 data the Sun Management Center 3.6 setup process detects the saved Sun Management Center 3.0 data and gives you the option to migrate the data to Sun Management Center 3.6.

▼ To Upgrade From Sun Management Center 3.0

Note – This procedure assumes that you installed Sun Management Center server in the default directory `/opt`. If you installed Sun Management Center in a different directory, substitute `/opt` with the name of the directory you specified.

- Steps**
1. **Log in as root on the machine where the Sun Management Center 3.0 server is installed.**
 2. **Stop Sun Management Center processes.**
Type the command `es-stop -A`. Wait until all Sun Management Center processes have been stopped.

3. Prepare the system for Sun Management Center 3.6 as described in [Chapter 4](#).

4. Upgrade the Solaris operating environment if necessary.

If you are upgrading the Sun Management Center 3.0 server, the machine must be running either the Solaris version 8 or Solaris version 9 developer environment. For additional information, see [“Prerequisite Packages” on page 76](#)



Caution – If you need to upgrade to Solaris version 8 or Solaris version 9, make sure you perform a Solaris upgrade. A fresh Solaris installation reformats the hard drive, which deletes your Sun Management Center 3.0 configuration data. If you perform a fresh Solaris installation, you will not be able to migrate your Sun Management Center 3.0 configuration data to Sun Management Center 3.6.

a. Back up all Sun Management Center 3.0 directories.

Tip – Use `ufsdump` to back up the Sun Management Center 3.0 directories to a different machine or backup device. `ufsdump` preserves symbolic links.

Sun Management Center 3.0 software is installed by default in `/opt/SUNWsymon`, `/var/opt/SUNWsymon`, and `/etc/opt/SUNWsymon` directories.

- If Sun Management Center 3.0 software has been installed to non-default locations, examine the Sun Management Center 3.0 installation logs in `/var/opt/SUNWsymon/install` to determine where Sun Management Center 3.0 software has been installed.
- If `/var/opt/SUNWsymon/install` does not contain the installation logs, or if `/var/opt/SUNWsymon` does not exist, you must determine where the Sun Management Center 3.0 software has been installed.

Sun Management Center software is installed as *install-path*/`SUNWsymon`, where *install-path* is the parent directory hierarchy.

For example, the Sun Management Center 3.0 core software could be installed in `/export/applications/SUNWsymon`. In this example, `/export/applications` is the *install-path*.

To determine where the Sun Management Center 3.0 software has been installed, search for all `SUNWsymon` directories on the system as follows:

i. Type the command `pkgparam SUNWescom BASEDIR` to determine the Sun Management Center 3.0 base directory. For example:

```
# pkgparam SUNWescom BASEDIR
/system/opt
```


- ii. Type the command `find / -name "SUNWsymon" -print` to locate the Sun Management Center configuration directories.
 - b. Upgrade the Solaris operating environment.
Refer to your Solaris documentation for procedures.
 - c. If necessary, restore the Sun Management Center 3.0 directories to the machine.
5. Upgrade the Sun Management Center 3.0 server to Sun Management Center 3.6 using any one of the following methods.
- To upgrade to Sun Management Center 3.6 using `es-guiinst`, follow the procedures in [“Installing Sun Management Center” on page 29](#).
 - To upgrade to Sun Management Center 3.6 using `es-inst`, follow the procedures in [“Installing Sun Management Center Using es-inst” on page 217](#).
 - To upgrade to Sun Management Center 3.6 by first uninstalling the Sun Management Center 3.0 configuration data, follow the procedures in [“Uninstalling Sun Management Center 3.0” on page 207](#).

Upgrade from 3.5 to 3.5 Update 1 or Update 2

Upgrading from Sun Management Center 3.5 to Sun Management Center 3.5 Update 1 or Update 2 is similar to the upgrading procedure from Sun Management Center 3.0 to Sun Management Center 3.5.

You can also upgrade from Sun Management Center 3.0 to Sun Management Center 3.5 Update 1.

On an installed, set up, and running Sun Management Center 3.5 host, do the following:

1. Run `es-inst` from the 3.5 Update 1 source image.
The installation wizard automatically launches the uninstallation wizard. The script uninstalls Sun Management Center 3.5 and asks you whether to preserve the data.
2. Type **y** to preserve the data.
After uninstallation of Sun Management Center 3.5 components, the new packages for Update 1 are installed. The Installer takes you to setup. The setup detects the preserved data and asks you whether or not to migrate the data.
3. Type **y** to migrate the data.

The upgrade procedure is complete.

Upgrade from 3.5 Update 1 or Update 2 to 3.6

Upgrading from Sun Management Center 3.5 Update 1 or Update 2 to Sun Management Center 3.6 is similar to the upgrading procedure from Sun Management Center 3.5 to Sun Management Center 3.5 update 1 or 2.

You can also upgrade from Sun Management Center 3.0 to Sun Management Center 3.6.

On an installed, set up, and running Sun Management Center 3.5 update 1 or 2 host, do the following:

1. Run `es-inst` from the 3.6 source image.
The installation wizard automatically launches the uninstallation wizard. The script uninstalls Sun Management Center 3.5 update 1 or 2 and asks you whether to preserve the data.
 2. Type `y` to preserve the data.
After uninstallation of Sun Management Center 3.5 update 1 or 2 components, the new packages for 3.6 are installed. The Installer takes you to setup. The setup detects the preserved data and asks you whether or not to migrate the data.
 3. Type `y` to migrate the data.
The upgrade procedure is complete.
-

Upgrading Agents

You can upgrade the Sun Management Center 3.0 agent to the Sun Management Center 3.6 agent using either of the following methods.

- Create an agent-only installation image on the Sun Management Center server as described in [“To Create an Agent-Only Installation Image Using `es-makeagent`”](#) on page 119. When you have created the agent-only installation image, apply the image to the agent hosts using the `es-inst -a` command as described in [“To Install Agents From an Agent-Only Installation Image Using `es-inst -a`”](#) on page 124.
- Create an agent-update image using either `es-gui-imagetool` as described in [“To Create an Agent-Update Image Using `es-gui-imagetool`”](#) on page 103, or by using `es-imagetool` as described in [“To Create an Agent-Update Image Using](#)

`es-imagetool`" on page 108. When you have created the agent-update image, apply the image to the agent hosts using the `agent-update.bin` executable file as described in "To Install or Update Agents From an Agent-Update Image Using `agent-update.bin`" on page 122.

Installing and Updating Agents and Installing on Microsoft Windows

This chapter provides the procedures for installing and updating agents.

This chapter discusses the following topics:

- “Creating Agent Installation and Update Images” on page 101
- “Applying Agent Installation, Update, and Patch-Only Images” on page 121
- “Installing Agents Using JumpStart” on page 126
- “Configuring Server and Agent on Multi-IP Machines” on page 148
- “Installing Sun Management Center 3.6 on Microsoft Windows” on page 153



Caution – Before you install Sun Management Center 3.6 using `es-guiinst`, ensure that you have completed all the tasks listed by “Preinstallation Checklist” on page 74.

Creating Agent Installation and Update Images

Agent-update images are supported on systems that have the Sun Management Center agent *only* installed. If you try to use agent-update images on systems where you have the Sun Management Center server or console or all three layers installed, the operation fails. Sun Management Center provides three tools to create agent-update images that can be used to install or simultaneously update Sun Management Center agents on multiple systems. The script and GUI image tool utilities also enable you to create patch-only update images that can be used to update multiple systems.

- `es-gui-imagetool` creates an agent-update image or a patch-only image using a graphical interface.

- `es-imagetool` creates an agent-update image or a patch-only image using a command-line interface.
- `es-makeagent` creates an agent-only installation image that includes support files for each version of the Solaris software and add-ons that were included on the installation CDs. The agent is installed on target machines by applying the agent-only image using the command, the `es-inst -a` command, or by using the JumpStart software.

`es-gui-imagetool` and `es-imagetool` enable you to select specific Solaris and Linux operating environments and add-ons, resulting in a much smaller installation image than the image created by `es-makeagent`. Images created using the image tools are applied by using the Sun Management Center Java console Manage Jobs task, or by using the `agent-update.bin` executable file.

Note – The Manage Jobs task enables you to apply the agent-update image to the target machines without performing any tasks on the target machines. Alternatively, you could copy or use ftp to copy the `agent-update.bin` executable file to each target machine, and then run the `agent-update.bin` on each target machine to apply the agent-update image.

The image type that you create depends on the following factors.

- If you want to update the Sun Management Center 3.6 agent on the target machines, create an agent-update image using either `es-gui-imagetool` or `es-imagetool`. When the agent-update image has been created, use the `agent-update.bin` executable file to apply the agent-update image to the target machines.
- If you want to install add-on agent components, or add-on components and patches on Sun Management Center 3.6 agent machines, create an agent-update image using either `es-gui-imagetool` or `es-imagetool`. When the agent-update image has been created, use the Manage Jobs task or the `agent-update.bin` executable file to apply the agent-update image to the target machines.
- If you want to apply patches only to the agent machines, create a patch-only update image using either `es-gui-imagetool` or `es-imagetool`. When the patch-only image has been created, use the Manage Jobs task or the `agent-update.bin` executable file to apply the patch-only image to the target machines.
- If you want to use JumpStart to install the Solaris operating environment and the Sun Management Center 3.6 agent on the target machines, create an agent-only image using `es-makeagent`. When you have created the agent-only update image, install the Solaris operating environment and the Sun Management Center 3.6 agent on the target machines as described in [“Installing Agents Using JumpStart”](#) on page 126.

The Sun Management Center 3.6 can be installed on SPARC, x86, and on Linux systems.

The following procedures describe how to create agent-update images and patch-only update images using `es-gui-imagetool` or `es-imagetool`, and how to create an agent-only image using `es-makeagent`.

▼ To Create an Agent-Update Image Using `es-gui-imagetool`

`es-gui-imagetool` enables you to create agent-update images containing any one of the following items.

- Base agent packages
- Add-on agent packages
- Base and add-on agent packages
- Base agent patches and add-on agent patches only

Note – This procedure assumes that you installed Sun Management Center in the default directory `/opt`. If you installed Sun Management Center in a different directory, replace `/opt` with the name of the directory you specified.

- Steps**
1. **Log in as root on the Sun Management Center 3.6 server machine.**
 2. **Run the Sun Management Center GUI image tool by typing the following command:**

```
# /opt/SUNWsymon/sbin/es-gui-imagetool
```

The Welcome screen appears. Click Next. The Overview screen appears, listing the information that you might need to provide. Click Next.

The Select Update-Image Components screen appears.

3. **Select the update-image components.**

Four choices are provided:

- Base Agent Packages
- Add-on Agent Packages
- Base and Add-on Agent Packages
- Base and Add-on Agent Patches Only

Note – Any patches needed for a selected package are automatically included when you select the package. If you want to install base agent patches and add-on agent patches only, select Base and Add-on Agent Patches Only.

Select the type of update-image that you want to create, and then click Next. The Specify the Installation Files Source Directory screen appears.

4. Provide the name of a valid Sun Management Center 3.6 source directory.

The installation source default `<DiskMountDir>/image` is displayed.

- If you are installing from CDs, insert Sun Management Center 3.6 CD 1 of 2 in the CD-ROM drive.

Enter a valid source directory: `<DiskMountDir>/image`

- If you are installing from a Sun Management Center 3.6 installation image on disk, either click Browse to navigate to the Sun Management Center installation `disk1/image` directory, or type the path to the `disk1/image` directory in the Source Directory field.

Source Directory: `/net/machine/installdir/disk1/image`

where *machine* is the machine on which you created the installation image, and *installdir* is the directory containing the Sun Management Center 3.6 disk1 and disk2 CD images. See “[Determining the Installation Source](#)” on page 85 for further information about installation images.

Click Next.

- If you selected Base Agent Packages, or selected Base and Add-on Agent Packages, the Specify the Destination Directory screen appears. Go to [Step 5](#).
- If you selected Add-on Agent Packages or Base and Add-on Agent Patches Only, the Update Image Name screen appears. Go to [Step 6](#).

5. Provide the target directory for Sun Management Center 3.6 installation.

The target directory is the directory where the Sun Management Center 3.6 SUNWsymon directory is created if it does not already exist.

- If an agent is not installed, then the new agent is installed in the directory you specify.
- If an older version of an agent is already installed in a different directory, then the new agent is installed in the directory you specify.
- If the same version of an agent is already installed in a different directory and the update you are applying contains additional components such as add-ons, the agent is updated in the existing directory.

The following scenario provides an example.

Assume you have created a base and add-on agent packages update image, and you have specified `/opt` as the target directory. Also, assume that you want to apply the update image to five different machines in the following states:

- Sun Management Center 3.0 is installed in `/opt/SUNWsymon` on machine A.
- Sun Management Center 3.0 is installed in `/export/home/opt/SUNWsymon` on machine B.
- No Sun Management Center components are installed on machine C.
- The Sun Management Center 3.5 base agent only is installed in `/opt/SUNWsymon` on machine D.
- The Sun Management Center 3.5 base agent only is installed in `/export/home/opt/SUNWsymon` on machine E.

When you apply the Sun Management Center 3.6 base and add-on agent packages update image to the five machines, each machine is updated as follows.

- On machine A, the Sun Management Center 3.6 agent is reinstalled and replaces the version 3.0 agent in directory `/opt/SUNWsymon`.
- On machine B, the Sun Management Center 3.6 agent is installed in directory `/opt/SUNWsymon`.
- On machine C, the Sun Management Center 3.6 agent is installed in directory `/opt/SUNWsymon`.
- On machine D, the base agent is upgraded, with add-on packages, to version 3.6 in directory `/opt/SUNWsymon`.
- On machine E, the base agent is upgraded, with add-on packages, to version 3.6 in directory `/export/home/opt/SUNWsymon`.

Click Next. The Sun Management Center Update-Image Name screen appears.

6. Provide a name for the agent update-image.

Type a name for the update-image that reflects the update-image type, for example `SPARC-Base-agents`, `x86-Base-agents`, `Linux agents add-ons` or `config-readers`.

The update-image is created in `/var/opt/SUNWsymon/agentupdate/update-image-name` where `update-image-name` is the name that you provide.

Click Next. The OS Selection screen appears.

7. Select the platform (Solaris or Linux) versions that the target machines are running.

The image tool will create images for all platform versions supported by Sun Management Center irrespective of the version of the machine on which the tool is running. You have a choice of selecting any of the platform versions, or all.



Caution – If you omit a platform version when you create an agent-update image, application of the update-image to the machine whose platform version is omitted will fail.

Click Next. The Checking for Available Products screen appears.

- If you selected Base Agent Packages, or Base and Add-on Agent Packages, the image tool verifies that all components of the base layer are available in the image source you specified.

When image source verification completes, the SNMP Port Assignment screen appears. Go to [Step 11](#).

- If you selected Add-on Packages, the Select Add-ons for Package and Patch Updates screen appears. Go to [Step 8](#).
- If you selected Base and Add-on Agent Patches, the Select Patches screen appears. Go to [Step 9](#).

8. Select Add-ons.

Select the products that you want to add to the agent update-image, and then click Next.

The image tool checks whether setup responses are needed by any of the add-on products you selected for inclusion in the update-image. Go to [Step 10](#).

- If the selected add-on products do not require setup responses, the SNMP Port Assignment screen appears. Go to [Step 11](#).
- If any selected add-on product requires setup responses, the Add-on Setup screen appears.

9. Select patches.

You can select all patches, or you can select individual patches.

When you have finished selecting patches, click Next. The Confirmation screen appears. [Step 12](#).

10. Provide add-on setup responses.

You are prompted to click Next to answer the setup questions for the selected add-on products. Click Next.

A terminal window appears, and the image tool process steps through each add-on product that you selected for agent update, and prompts you for the responses needed by each product. Refer to the documentation that is provided with each add-on for further information.

When you finish providing responses, the SNMP Port Assignment screen appears.

11. Specify an SNMP port for the Sun Management Center agent.

In most cases, port 161 is the default port assigned to and used by the SNMP daemon. However, other processes or daemons could be using port 161. Several third-party replacements and enhancements for the SNMP daemon exist, and could be installed on your system. The Sun Management Center agent is one such daemon. Also keep in mind that a port number other than 161 could have been specified during Sun Management Center setup on each target machine.

See [“To Determine Whether a Port Is Used” on page 184](#) for procedures on how to determine if a port is unused.



Caution – If you select port 161, you must stop and disable any process that uses port 161 on each target machine before you can restart the agent on each machine. Stopping and disabling the SNMP daemon on each machine is not a guarantee that you have stopped the actual process using port 161. To determine which daemon process uses port 161 requires you to manually review all `/etc/rcN` and `/etc/rcN.d` files, where `N` is 0 through 6 and `S`. When you have identified the file that defines the process using port 161, you can disable the process by renaming the file. For example,

```
/etc/rc3.d# mv s76snmpdx s76snmpdx
```

You must disable any daemon that uses port 161 on each target machine.

- To use port 161 on each target machine, select Use Port 161, and then click Next. The Stop and Disable SNMP Daemon screen appears.
- To assign a different port number, select Use A Different Port Number. Type the port number in the Port ID field and then click Next. When the agent-update image is applied on the target client, the update process checks whether an agent is already installed.
 - If an agent was previously installed and configured, the update process uses the original port assignment. For example, if the previous agent uses port 2261, then the update process assigns port 2261 to the updated agent.
 - If an agent is not installed and port 161 is not in use, the update process assigns port 161 to the agent .
 - If an agent is not installed and port 161 is in use, the update process assigns the port you specified to the agent .

The image tool process now checks for sufficient disk space.

- If there is not enough space to create the image, you are notified. The amount of free space that is needed is listed. Click Cancel to exit the update-image tool. You must increase the amount of free space by the amount listed before you can create an update-image.
- If there is enough disk space, the Confirmation screen is displayed.

12. Confirm update-image selections

A list of the components that you selected for inclusion in the agent update-image is displayed.

- If the list is not correct, click Back repeatedly to return to either the Select Add-ons for Package and Patch Updates screen, or to the Select Update-Image Components screen. When the appropriate screen is displayed, select the products that you want to add to the update-image and confirm your new selections.
- If the list is correct, click Next.

The image tool creates the agent update-image in the directory `/var/opt/SUNWsymon/agentupdate` using the file name you specified in [Step 6](#).

You are notified when the update image has been created. Click Close to return to the system prompt.

You can check the update image creation status by viewing the log file `/var/opt/SUNWsymon/install/es-gui-imagetool_<host-name>.<date-and-time-string>.<process-id>` where:

- *host-name* is the name of the Sun Management Center 3.6 server that you used to create the update image.
- *date-and-time-string* is the year, date, and time the image was created.
- *process-id* is the process ID of the imagetool session that created the agent-update image.

13. Apply the agent-update image.

You can now apply the update-image to the target machines.

- To upgrade Sun Management Center 3.0 agents, apply the image using the `agent-update.bin` executable file, see [“To Install or Update Agents From an Agent-Update Image Using agent-update.bin”](#) on page 122.
- To upgrade Sun Management Center 3.5 Update 2 agents, apply the image using the Sun Management Center task manager, see [“To Create an Agent Update Task”](#) in *Sun Management Center 3.6 User's Guide*.

▼ To Create an Agent-Update Image Using `es-imagetool`

`es-imagetool` enables you to create agent-update images containing any one of the following.

- Base agent packages
- Add-on agent packages
- Base and add-on agent packages

- Base agent patches and add-on agent patches only

Note – This procedure assumes that you installed Sun Management Center in the default directory `/opt`. If you installed Sun Management Center in a different directory, replace `/opt` with the name of the directory you specified.

Steps 1. Log in as root on the Sun Management Center 3.6 server machine.

2. Run the Sun Management Center command-line image tool by typing the following command:

```
# /opt/SUNWsymon/sbin/es-imagetool
```

3. Select the components to update.

You are prompted to select the components that you want to add to the update-image, for example:

Select the components you want to add to the update-image.

```
Do you want to upgrade components of Base Agent? [y|n|q] y
```

```
Do you want to install/upgrade components of Addons? [y|n|q] y
```

Type **y** to add the component to the update-image, or type **n** to exclude the component from the update-image.

You are prompted for a valid source directory.

4. Provide the name of a valid Sun Management Center 3.6 source directory.

- If you are installing from CDs, type the path to the Sun Management Center 3.6 installation CD 1 image directory. For example:

```
Enter a valid source directory: /<DiskMountDir>/image
```

- If you are installing from a Sun Management Center 3.6 installation image on disk, type the path to the image `disk1/image` directory. For example:

```
Enter a valid source directory: /net/machine/installdir/disk1/image
```

where *machine* is the machine on which you created the installation image, and *installdir* is the directory containing the Sun Management Center 3.6 disk1 and disk2 CD images. See “[Determining the Installation Source](#)” on page 85 for further information about installation images.

- If you replied **y** to the prompt Do you want to upgrade components of the Base Agent?, you are prompted for the installation target directory. Go to [Step 5](#).
- If you replied **n** to the prompt Do you want to upgrade components of the Base Agent?, and replied **y** to the prompt Do you want to install/upgrade components of Addons?, you are prompted for the installation target directory. Go to [Step 6](#).

5. Provide the name of the target directory for Sun Management Center 3.6 installation.

The target directory is the directory where the Sun Management Center 3.6 SUNWsymon directory is created if it does not already exist.

- If an agent is not installed, then the new agent is installed in the directory you specify.
- If an older version of an agent is already installed in a different directory, then the new agent is installed in the directory you specify.
- If the same version of an agent is already installed in a different directory, and the update you are applying contains new software, the agent is updated in the existing directory.

The following scenario provides an example:

Assume that you have created a Base and Add-on Agent Packages update image, and that you have specified /opt as the target directory. Also, assume that you want to apply the update image to five different machines in the following states:

- Sun Management Center 3.0 is installed in /opt/SUNWsymon on machine A.
- Sun Management Center 3.0 is installed in /export/home/opt/SUNWsymon on machine B.
- No Sun Management Center components are installed on machine C.
- The Sun Management Center 3.5 base agent only is installed in /opt/SUNWsymon on machine D.
- The Sun Management Center 3.5 base agent only is installed in /export/home/opt/SUNWsymon on machine E.

When you apply the Sun Management Center 3.6 Base and Add-on Agent Packages update image to the five machines, each machine is updated as follows.

- On machine A, the Sun Management Center 3.6 agent is reinstalled and replaces the version 3.0 agent in directory /opt/SUNWsymon.
- On machine B, the Sun Management Center 3.6 agent is installed in directory /opt/SUNWsymon.
- On machine C, the Sun Management Center 3.6 agent is installed in directory /opt/SUNWsymon.
- On machine D, the base agent is upgraded, with add-on packages, to version 3.6 in directory /opt/SUNWsymon.
- On machine E, the base agent is upgraded, with add-on packages, to version 3.6 in directory /export/home/opt/SUNWsymon.

You are prompted for a name for the agent update image.

6. Provide a name for the agent update-image.

Provide a name for the update-image that reflects the update-image type, for example Ultra60agent, SPARC-baseagent, x86-baseagent, or Linux agent and then press Return.

The update-image is created in `/var/opt/SUNWsymon/agentupdate/update-image-name`, where *update-image-name* is the name that you provide.

You are then prompted to choose the platform (Solaris or Linux) versions for the target machines.

The image tool creates images for all platform versions supported by Sun Management Center irrespective of the platform version on the machine on which the tool is running. You have a choice of selecting any Solaris version or all versions.

7. Select the platforms that the target machines are running.

The supported versions are listed, and you are asked whether you want to select all versions.

- Reply **y** if the target machines include all Solaris and Linux versions.

The image tool process checks for available add-on products. Go to [Step 8](#).

- Reply **n** if the target machines do not include all versions.

Each version of Solaris and Linux is listed, and you are asked whether you want to create an image for that version. Reply **y** or **n** as appropriate for the target machines. For example:

```
Do you want to select ALL OS versions ? [y|n|q] n

Do you want to create images for sparc-sun-Solaris_2.6 ? [y|n|q] n
Do you want to create images for sparc-sun-Solaris_7 ? [y|n|q] n
Do you want to create images for sparc-sun-Solaris_8 ? [y|n|q] y
Do you want to create images for sparc-sun-Solaris_9 ? [y|n|q] n
Do you want to create images for sparc-sun-Solaris_10 ? [y|n|q] y
Do you want to create images for i386-sun-Solaris_9 ? [y|n|q] n
Do you want to create images for i386-sun-Solaris_10 ? [y|n|q] y
Do you want to create images for i686-sun-Linux_2.4 ? [y|n|q] y
Do you want to create images for i686-sun-Linux_2.6 ? [y|n|q] n
```



Caution – If you omit a Solaris version when you create an agent-update image, application of the update-image to the machine whose Solaris version is omitted will fail.

- If you selected only Upgrade Components of Base Agent in [Step 3](#), go to [Step 9](#).
- If you selected Install/upgrade Components of Addons in [Step 3](#), the image tool process checks the add-on products and lists the products for which an agent update is available. Go to [Step 8](#).

8. Select the agent add-on products that you want to upgrade.

The available add-on products are listed, and you are then sequentially asked whether you want to install each add-on product. Reply **y** to add the add-on software to the update-image, or reply **n** to exclude the add-on software from the image.

When you finish selecting the add-on products to upgrade, you are prompted for the Sun Management Center agent port.

9. Specify a port for the Sun Management Center agent.

In most cases, port 161 is the default port assigned to and used by the SNMP daemon. However, other processes or daemons could be using port 161. Several third-party replacements and enhancements for the SNMP daemon exist, and could be installed on your system. The Sun Management Center agent is such a daemon. A different port number could have been specified during Sun Management Center on each target machine.



Caution – If you select port 161, you must stop and disable any process that uses port 161 on each target machine before you can restart the agent on each machine. Stopping and disabling the SNMP daemon on each machine is not a guarantee that you have stopped the actual process using port 161. Determining the actual daemon process that uses port 161 requires you to manually review all `/etc/rcN` and `/etc/rcN.d` files, where *N* is 0 through 6 and *S*. When you have identified the file that defines the process using port 161, you can disable the process by renaming the file. For example,

```
/etc/rc3.d# mv S76snmpdx S76snmpdx
```

You must disable the daemon that uses port 161 on each target machine.

Press Return to use port 161 on each target machine, or type a different port number.

- If you selected only Upgrade Components of Base Agent in [Step 3](#), the image tool process checks for sufficient disk space. If there is enough space, the agent update-image is created.
If there is not enough space to create the image, you are notified. The amount of free space that is needed is displayed. The image tool exits. You must increase the amount of free space by the amount listed before you can create an update-image.
- If you selected `install/upgrade components of Addons` in [Step 3](#), the image tool process checks whether setup responses are needed by any of the add-on products that you selected for inclusion in the update-image.
If any selected product requires setup responses, the image tool process steps through each add-on product that you selected for update, and prompts you for the responses needed by each product. Refer to the documentation that is

provided with each add-on for further information.

When add-on product setup response collection is completed, the image tool checks disk space. If there is enough space, the agent update-image is created.

If there is not enough space to create the image, you are notified. The amount of free space that is needed is displayed. The image tool exits. You must increase the amount of free space by the amount listed before you can create an update-image.

You are notified when the update-image has been created. You can check the update image creation status by viewing the log file

```
/var/opt/SUNWsymon/install/  
es-imagetool_host-name.date-and-time-string.process-id where:
```

- *host-name* is the name of the Sun Management Center 3.6 server that you used to create the update image.
- *date-and-time-string* is the year, date, and time that the image was created.
- *process-id* is the process ID of the imagetool session that created the agent-update image.

You can now apply the image to the target machines.

- To upgrade Sun Management Center 3.5 Update 2 agents, apply the image using the Sun Management Center task manager, see “To Create an Agent Update Task” in *Sun Management Center 3.6 User’s Guide*.
- To upgrade Sun Management Center 3.0 agents, apply the image using the `agent-update.bin` executable file, see “To Install or Update Agents From an Agent-Update Image Using `agent-update.bin`” on page 122.

▼ To Create a Patch-Only Image Using the Image Tools

Sun Management Center-specific patches are released periodically on the Sun Management Center website at <http://www.sun.com/sunmanagementcenter>. Sun Management Center enables you to create a patch-only image, and then apply the patch-only image to multiple agent machines.

- Steps**
1. **Log in as root on the Sun Management Center 3.6 server machine.**
 2. **Create a directory in which to download the Sun Management Center patches.**
Change to the directory you just created. Create directories for each Solaris operating environment version for which you want to download patches.

For example, assume you created the directory `/sunmcpatches`. Furthermore, assume you plan to create patch-only update images for each supported Solaris version. You would create the directories as follows.

```
# mkdir /sunmcpatches
# cd /sunmcpatches
/sunmcpatches # mkdir Solaris_2.6 Solaris_7 Solaris_8 Solaris_9
```

The directories must be created using the names shown.

3. Determine which Sun Management Center patches are available for download.

Open a browser and go to <http://www.sun.com/sunmanagementcenter>. Click the `Patches` and `Support` link.

Review the list of available patches that is displayed at the bottom of the page. Print the page so that you can reference the patch numbers.

4. Log on to SunSolve.

Click the `Login` button to display the login screen, and then enter your SunSolve ID and password.

If you do not have a SunSolve ID, click the `Register` button to obtain a SunSolve ID.

5. Download the patches for each Solaris version.

Click the patch number corresponding to the Solaris version.

The SunSolve Online Web page is displayed.

a. Type the number of the patch you want to view, and then click Find Patch.

A description of the patch is displayed.

Make note of the supported Solaris versions. If the patch applies to more than one Solaris version, you must download the patch file for each Solaris version.

b. Click either the HTTP or FTP download link to download the patch.

The `Save As` panel appears.

Save the patch file to the applicable Solaris version directory you created in [Step 2](#).

For example, assume patch 111222-33 is applicable to Solaris version 8 and Solaris version 9. Assume that you also created the subdirectories `Solaris_8` and `Solaris_9` within the root directory `sunmcpatches`. You would then download the patch file to both `/sunmcpatches/Solaris_8` and `/sunmcpatches/Solaris_9`.

If you want to download more patches, click `Back` to return to the SunSolve Online Web page. Repeat the previous two steps to download each patch you have selected.

When you have completed downloading patches, go to the next step.

6. Uncompress the patch files.

Change to each directory where you downloaded the patch files and uncompress the files.

For example, assume you downloaded the patch file for patch 111222-33 and patch 111222-34 to `/sunmcpatches/Solaris_8`. Also assume that the patch file for patch file 111222-33 is `111222-33.tar.Z`, and the patch file for 111222-34 is `111222-34.zip`. You would then uncompress the patch files as follows:

```
/sunmcpatches # cd Solaris_8
/sunmcpatches/Solaris_8 # ls
111222-33.tar.Z      111222-34.zip
/sunmcpatches/Solaris_8 # zcat 111222-33.tar.Z | tar xvf -
x 111222-33, 0 bytes, 0 tape blocks
x 111222-33/installpatch, 119239 bytes, 233 tape blocks
.
.
.
x 111222-33/README.111222-33, 136444 bytes, 267 tape blocks
/sunmcpatches/Solaris_8 # unzip 111222-34.zip
Archive: 111222-34.zip
  creating: 111222-34/
  ..inflating: 111222-34/prepatch
.
.
.
  inflating: 111222-34/README.111222-34
/sunmcpatches/Solaris_8 # ls -p
111222-33/      111222-33.tar.Z....111222-34/      111222-34.zip
```

You can create the patch-only image using either the graphical tool `es-gui-imagetool` as described next in [Step 8](#), or by using the command-line tool `es-imagetool` as described in [Step 9](#).

7. Move the download patch files to another directory.

Either move the compressed download patch files to another directory for safekeeping, or delete the compressed patch files.

8. Create the patch-only image file using `es-gui-imagetool`.

Note – The following steps assume that you installed Sun Management Center in the default directory `/opt`. If you installed Sun Management Center in a different directory, replace `/opt` with the name of the directory you specified.

a. Type the command `/opt/SUNWsymon/sbin/es-gui-imagetool`.

The Welcome screen appears. Click Next. The Overview screen appears. Click Next.

The Select Update-Image Options screen appears.

b. Select Base and Add-on Agent Patches Only.

Click Next.

The Specify the Installation Files Source Directory screen appears.

c. Specify the patch file source directory.

Type the name of the patch directory you created in [Step 2](#), or Click Browse to navigate to and select the directory.

Click Next. The Update Image Name screen appears.

d. Provide a name for the patch-only image.

Type a name for the patch-only image that reflects the image type, for example `base-and-addon-patches`.

The image is created in `/var/opt/SUNWsymon/agentupdate/update-image-name` where `update-image-name` is the name that you provide.

Click Next. The OS Selection screen appears.

e. Select the Solaris versions that the target machines are running.

The image tool will create images for all Solaris versions supported by Sun Management Center irrespective of the version of the machine on which the tool is running. You have a choice of selecting any of the Solaris versions, or all versions.



Caution – If you omit a Solaris version when you create a patch-only image, application of the patches to the machine whose Solaris version is omitted will fail.

Click Next. The Checking for Patches screen appears. When the image tool has completed checking for patches, the Select Patches screen appears.

f. Select the patches you want to add to the patch-only update image.

You can select all patches, or you can select individual patches.

When you have finished selecting patches, click Next. The image tool checks for disk space.

- If there is not enough space to create the image, you are notified. The amount of free space that is needed is listed. Click Cancel to exit the image tool. You must increase the amount of free space by the amount listed before you can create a patch-only image.
- If there is enough disk space, the Confirmation screen is displayed.

g. Confirm Update-Image Selections

A list of the patches and the Solaris versions that you selected for the patch-only image is displayed.

- If the list is not correct, click Back twice to return to the Solaris version selection screen, or click Back once to return to the Select Patches screen. Select the Solaris versions and patches that you want to add to the patch-only image and confirm your new selections.

- If the list is correct, click Next.

The image tool creates the patch-only image in the directory `/var/opt/SUNWsymon/agentupdate` using the file name you specified in [Step d](#).

You are notified when the update image has been created. Click Close to return to the system prompt.

You can check the update image creation status by viewing the log file `/var/opt/SUNWsymon/install/es-gui-imagetool_<host-name>.<date-and-time-string>.<process-id>` where:

- *host-name* is the name of the Sun Management Center 3.6 server that you used to create the update image.
- *date-and-time-string* is the year, date, and time the image was created.
- *process-id* is the process ID of the imagetool session that created the agent-update image.

h. Apply the patch-only image.

You can now apply the image to the target machines.

- To apply the image using the Sun Management Center task manager, see “To Create an Agent Update Task” in *Sun Management Center 3.6 User’s Guide*.
- To apply the image using `agent-update.bin` executable file, see “To Install or Update Agents From an Agent-Update Image Using `agent-update.bin`” on page 122.

9. Create the patch-only image file using `es-imagetool`.

Note – The following steps assume that you installed Sun Management Center in the default directory `/opt`. If you installed Sun Management Center in a different directory, replace `/opt` with the name of the directory you specified.

a. Type the command `/opt/SUNWsymon/sbin/es-imagetool`.

You are asked whether you want to upgrade components of the Base agent. Type `n` and press Return.

You are asked whether you want to install or upgrade components of add-ons. Type **n** and press Return.

You are asked whether you want to install patches. Type **y** and press Return.

You are prompted for the patch-only source directory.

b. Specify the patch file source directory.

Type the name of the patch directory you created in [Step 2](#), and then press Return.

You are prompted to provide a name for the patch-only image.

c. Provide a name for the patch-only image.

Type a name for the patch-only image that reflects the image type, for example `base-and-addon-patches`.

The image is created in `/var/opt/SUNWsymon/agentupdate/update-image-name` where `update-image-name` is the name that you provide.

Press Return. The supported Solaris versions are listed.

d. Select the Solaris versions that the target machines are running.

The image tool will create images for all Solaris versions supported by Sun Management Center irrespective of the version of the machine on which the tool is running. You have a choice of selecting any Solaris version, or all versions.



Caution – If you omit a Solaris version when you create an patch-only image, application of the patches to the machine whose Solaris version is omitted will fail.

- To select all Solaris versions, type **y**.

- To select only specific Solaris versions, type **n**.

You are prompted to select each Solaris version sequentially. Type **y** to select a Solaris version, or type **n** to exclude the Solaris version from the image.

Press Return. The image tool lists the patches that are available for selection.

e. Select the patches that you want to add to the patch-only update image.

You are prompted to select each patch.

Type **y** to select a patch for inclusion in the patch-only image, or type **n** to exclude the patch from the image.

When you have completed selecting patches, press Return. The image tool checks for disk space.

- If there is not enough space to create the image, you are notified. The amount of free space that is needed is listed. Type **q** to exit the image tool. You must increase the amount of free space by the amount listed before you can create a patch-only image.
- If there is enough disk space, the patch-only image is created in the directory `/var/opt/SUNWsymon/agentupdate` using the file name that you specified in [Step c](#).

You can check the update image creation status by viewing the log file `/var/opt/SUNWsymon/install/es-imagetool_<host-name>.<date-and-time-string>.<process-id>` where:

- *host-name* is the name of the Sun Management Center 3.6 server that you used to create the update image.
- *date-and-time-string* is the year, date, and time the image was created.
- *process-id* is the process ID of the imagetool session that created the agent-update image.

f. Apply the patch-only image.

You can now apply the image to the target machines.

- To apply the image using the Sun Management Center Task Manager, see “To Create an Agent Update Task” in *Sun Management Center 3.6 User’s Guide*.
- To apply the image using the `agent-update.bin` executable file, see “To Install or Update Agents From an Agent-Update Image Using `agent-update.bin`” on page 122.

▼ To Create an Agent-Only Installation Image Using `es-makeagent`

Note – This procedure assumes that you installed Sun Management Center in the default directory `/opt`. If you installed Sun Management Center in a different directory, replace `/opt` with the name of the directory you specified.

- Steps**
1. **Log in as root.**
 2. **Place Sun Management Center 3.6 CD 1 of 2 in the CD-ROM drive.**
 3. **Type the command `/opt/SUNWsymon/sbin/es-makeagent`.**
You are prompted for the installation source files directory.

4. Type the source directory:

(SPARC) /<DiskMountDir>/image/SunOS/sparc

(x86) /<DiskMountDir>/image/SunOS/i386

(Linux) /<DiskMountDir>/image/Linux

You are asked for a target directory in which to create the agent-only installation image.

5. Type the name of the target directory.

If the directory does not exist, you are asked whether you want to create it. Type **y** to create the directory, or type **n** or **q** to exit to the system prompt.

The directory you specify must have write permission for root.

For example:

```
# enter the target directory: /es-makeagent-image
Directory /es-makeagent-image does not exist
Do you want to create it (y|n|q) y
```

The `es-makeagent` script creates the subdirectories `disk1` and `disk2` in the directory you specified, and then copies the files required to the subdirectories.

When `es-makeagent` completes copying files from Sun Management Center 3.6 installation CD 1 of 2, the CD is ejected, and you are prompted to insert the second CD or specify the source directory for disk 2.

a. Remove the first Sun Management Center installation CD.

Place the Sun Management Center 3.6 CD 2 of 2 in the CD-ROM drive, then close the drive.

b. When the CD-ROM drive LED turns off, press Return.

`es-makeagent` copies the remaining files from the CD.

You are informed that the agent-only product is available in the directory you specified. The command required to install the agent on the local machine is also displayed.

Tip – Mount the target directory using NFS, so that the directory is accessible by other machines on your network. See [Step 12](#) in “To Create CD Images” on page 85.

6. Type the command `eject` to eject the CD.

You can now install the Sun Management Center 3.6 agent using any of the following methods.

- Use the `es-inst -a` command as described in [“To Install Agents From an Agent-Only Installation Image Using `es-inst -a`”](#) on page 124. When prompted for the installation source directory, provide the name of the agent-only installation image that you specified in [Step 5](#). Make sure that you have shared the agent-only installation image by using Network File Sharing.
- Apply the agent-only installation image using the JumpStart software as described in [“Installing Agents Using JumpStart”](#) on page 126.

Note – The agent-only installation image also contains a tar file that you can copy using `ftp` to other agent machines and uncompress on each agent machine to create an installation image. The uncompressed installation image directory contains the subdirectories `disk1` and `disk2`. To install from the uncompressed image on each agent machine, change directory to the `disk1/sbin` directory, and use the `es-inst` command as described in [“Installing Sun Management Center Using `es-inst`”](#) on page 217.

Applying Agent Installation, Update, and Patch-Only Images

The following procedures describe how to install or update agents from agent-update images using the Manage Jobs task, and the `agent-update.bin` executable file, and how to install agent-only installation images using the `es-inst -a` command.

Note – If you want to use the JumpStart software to install the Solaris operating environment and the agent, see [“Installing Agents Using JumpStart”](#) on page 126.

▼ To Install Agents From an Agent-Update Image Using the Manage Jobs Task

If you want to upgrade Sun Management Center 3.0 agents, apply the agent-update image by using the `agent-update.bin` executable file as described in [“To Install or Update Agents From an Agent-Update Image Using `agent-update.bin`”](#) on page 122. The Manage Jobs task is used to upgrade existing Sun Management Center 3.6 agents.

- Steps** 1. Create an agent-update image using either of the image tools.

- To create an agent-update image using `es-gui-imagetool`, follow the instructions in “To Create an Agent-Update Image Using `es-gui-imagetool`” on page 103.
 - To create an agent-update image using `es-imagetool`, follow the instructions in “To Create an Agent-Update Image Using `es-imagetool`” on page 108.
2. **Start the Sun Management Center console, and then log in to the console as an authorized Sun Management Center user.**
See “To Start the Console on the Solaris Platform” on page 168.
 3. **Choose Tools → Manage Jobs.**
The Manage Jobs window is displayed.

The Manage Jobs window enables you to propagate your agents on multiple hosts simultaneously. For further details on the Manage Jobs feature, refer to the *Sun Management Center 3.6 User’s Guide*.
 4. **Create a multiple-agent upgrade task.**

Note – Make sure the Sun Management Center agent is installed and running on the target hosts.

a. Select target hosts for upgrades, and then create a group.

b. Create a task of type Agent Update

Select an appropriate image name for the upgrade operation. This name should be the name of an image you created using either the `es-imagetool` or the `es-gui-imagetool`.

For detailed instructions, see “To Create an Agent Update Task” in *Sun Management Center 3.6 User’s Guide*

The status displayed in the Job Manager window only shows the success or failure of the entire job. The job is marked Failed if the upgrade fails on a single agent in the entire group, even though the rest of the agent upgrades succeeded. Click View Log next to the Job list to check the status of individual upgrades.

To view the intermediate upgrade status while the job is in progress, click View Logs tab, and then click `InstallServer.log`.

▼ To Install or Update Agents From an Agent-Update Image Using `agent-update.bin`

The space requirements on the target machine `/tmp` directory are as follows depending on the contents of the update-image:

- Base agent only - 115 Mbytes to 125 Mbytes
- Base agent and Add-ons - 200 Mbytes to 210 Mbytes
- Add-ons or patches only - less than 100 Mbytes

If you use a *seed-file* to specify the security seed and SNMP community string automatically, the *seed-file* must have the following format:

```
ES_SECURITY_SEED=<seed>
ES_SNMPV1_STRING=<string>
```

where *seed* and *string* are the actual seed and community string specified when the Sun Management Center server was installed. If you do not specify a value for `ES_SNMPV1_STRING`, the default SNMP value is used. In this case, the file will be:

```
ES_SECURITY_SEED=<seed>
ES_SNMPV1_STRING=<string>
```

Steps 1. Log in as root on the Sun Management Center server machine.

2. Create an agent-update image using either of the image tools.

- To create an agent-update image using `es-gui-imagetool`, follow the instructions in [“To Create an Agent-Update Image Using es-gui-imagetool”](#) on page 103.
- To create an agent-update image using `es-imagetool`, follow the instructions in [“To Create an Agent-Update Image Using es-imagetool”](#) on page 108.

3. Download the relevant agent-update.bin file from the Sun Management Center server to each target machine’s root directory.

- (SPARC) `/opt/SUNWsymon/base/bin/sparc-sun-solaris/agent-update.bin`
- (x86) `/opt/SUNWsymon/base/bin/i386-sun-solaris/agent-update.bin`
- (Linux) `/opt/SUNWsymon/base/bin/i686-sun-Linux/agent-update.bin`

If you installed Sun Management Center in a different directory than `/opt`, replace the `/opt` with *installdir* in the paths mentioned, where *installdir* is the directory you specified. This step must be performed for each target machine.

When you have finished downloading the file `agent-update.bin` to each target machine, you must log in to each target machine and perform the following four steps on each machine.

4. Log in as root on the target machine.

5. Change to the directory where you downloaded agent-update.bin.

6. Type this command:

```
./agent-update.bin -s server -r http-port -p image-name [-f seed-file]
```

where

- *server* is the server that you logged into in [Step 1](#)
- *http-port* is the Sun Management Center Web server port.
- *image-name* is the name of the agent-only image you created in [Step 2](#)
- *seed-file* is a file containing the security seed and SNMP community string. By using this option, you can make agent installation automatic after running the command. The *seed-file* must be owned by root and have read/write permissions for root only as a security precaution. If the file does not meet these requirements, the script exits.

For example, assume that the Sun Management Center server name is `Production1` and that the Web server port is 8080. Also, assume that the agent-update image name is `sparc-baseagent`. You would then type:

```
# ./agent-update.bin -s Production1 -r 8080 -p sparc-baseagent
```

7. Provide the security seed and the SNMPv1 community string.

The agent-update process prompts you for the security seed and the SNMPv1 community string.

- The security seed must be the same seed that you provided when you set up the Sun Management Center server and agent.
Type the security seed password that you provided in [Step b](#), “[Setting Up Sun Management Center](#)” on page 33. Type the password again to confirm the password.
- The SNMPv1 community string must be the same community string you provided when you set up the Sun Management Center server and agent.
If you specified a custom community string, make sure that you type the same community string that you provided in “[Setting Up Sun Management Center](#)” on page 33, [Step c](#). If you used the default community string of `public`, press Return.

The update process applies the update to the machine without prompting for further information.

When the update process completes, check the update status by viewing the log file `/var/opt/SUNWsymon/log/agent-update.log` on the target machine.

▼ To Install Agents From an Agent-Only Installation Image Using `es-inst -a`

- Steps**
1. Create an agent-only installation image as directed in “[To Create an Agent-Only Installation Image Using `es-makeagent`](#)” on page 119.
 2. Log in as root on the machine where you want to install the agent.

3. Go to the agent-only install image `disk1/sbin` directory.

For example, if you created the agent-only image in the `/export/agentsource` directory on a machine that is named `appserver`, you would type:

```
# cd /net/appserver/export/agentsource/disk1/sbin
```

4. Type the command `./es-inst -a` to install the Sun Management Center agent.

You are prompted for the target directory

5. Type the name of the directory in which to install Sun Management Center

The default location is `/opt`.

Sun Management Center software can be installed in any location on your system where the minimum required disk space is available. Press Return to accept the default location `/opt` or, if you want to install to a directory other than `/opt`, type the directory name.

Tip – The command `df -ak` lists the used space and free space for each file system on the machine.

The install process checks for any applicable add-ons.

6. Select the Sun Management Center add-on products.

The install process lists each add-on product, and asks whether you want to install the product.

Note – Only the agent component of a selected add-on is installed.

Type **y** to select the product for installation, or type **n** if you do not want to install the product.

If you did not select any add-on products, you are asked whether you want to proceed. Type **y** to continue. The install process checks disk space. Go to [Step 8](#).

If you selected any add-ons, your selections are listed.

7. Review your selections.

Type **y** to continue, or type **n** to repeat the selection process.

The install process checks disk space.

8. Check disk space.

The installation process checks whether there is enough disk space to install the agent and the agent component of any add-on that you selected.

- If there is enough disk space, the agent is installed. You are asked whether you want to run setup. Go to [Step 10](#).
- If there is not enough disk space, you are asked to provide an alternate file system. The amount of space available and the amount of space that is needed are displayed.

9. Provide the name of an alternate file system with enough disk space.

At the prompt requesting a different file system, type the name of a file system and directory that has enough free space.

Tip – In a terminal window on the machine where you are installing Sun Management Center, type `df -ak` to list the amount of used and free space for each file system on the machine.

The installation process checks disk space again. If there is enough disk space, the agent is installed. You are asked whether you want to run setup.

10. Decide whether to set up the agent.

To set up Sun Management Center agent and any add-on products that you selected, type `y`. Follow the instructions in [“To Set Up Sun Management Center” on page 33](#).

If you chose to run setup later, you must set up the agent on the machine before you can run the agent. Use either `es-guisetup` or `es-setup` to set up the agent.

- To setup the agent using `es-guisetup`, follow the instructions in [“To Set Up Sun Management Center” on page 33](#).
- To setup the agent using `es-setup`, follow the instructions in [“Setting Up Sun Management Center 3.6 Using es-setup” on page 230](#).

Installing Agents Using JumpStart

This section describes how to configure and use a Solaris JumpStart server to install and set up the Sun Management Center 3.6 base agent, and the Solaris version 8 or version 9 operating environment, on a large number of systems.

JumpStart Concepts

The JumpStart software enables you to automatically install or upgrade the Solaris operating environment on several systems, and to perform pre-install and post-install tasks that can include installation and setup of additional software such as Sun Management Center.

The Solaris JumpStart software is a client-server application that consists of the following components:

- Boot server – Provides a mini-root Solaris operating system kernel to the install client using trivial file transfer protocol (*tftp*). The kernel is architecture-neutral, and provides base services to all hardware supported by the Solaris version running on the boot server.
- Install server – Provides the software packages, such as the Sun Management Center 3.6 base agent, that are to be installed on the target systems or *install clients*.
- Install clients – The target systems on which Solaris and specified software packages, such as the Sun Management Center 3.6 base agent, are to be installed.
- Profile or configuration server – Provides JumpStart *profiles*.

A JumpStart profile is a text file that defines how the Solaris operating environment software is to be installed on each install client in a group. The JumpStart profile can be used to specify which software groups to install, and the partition specifications, space allocations, and backup media to be used during software upgrades.

You can create more than one JumpStart profile, such as one for a fresh install of the Solaris operating environment, and another for an upgrade install of the Solaris operating environment. Each JumpStart profile is assigned to one or more install clients using the JumpStart *rules* file.

For detailed information about creating a JumpStart profile, see “Creating a Profile” in *Solaris 9 9/04 Installation Guide*.

- Rules file – Specifies the tasks that are to be performed on an install client, or on a group of install clients. Each rule within the rules file specifies the following items:
 - An install client or group of install clients, consisting of a rule keyword or general system attribute, and a rule value or specific system attribute.
 - An optional begin script, which performs specific tasks before the Solaris operating environment is installed or upgraded
 - The JumpStart profile that is to be applied to each install client or group of install clients.
 - An optional finish script, which performs specific tasks after the Solaris operating environment has been installed or upgraded. A finish script is required to install the Sun Management Center base agent using the JumpStart software.

All install clients on which the Sun Management Center base agent is installed using a specific JumpStart rule will have an identical Sun Management Center configuration. The Sun Management Center root directory, server context, security seed, and SMNPv1 community string are identical.

You also need a separate machine, referred to as the *prototype* machine, on which to generate the Sun Management Center install and setup response files required by the JumpStart finish script. If Solstice SyMON 1.x, Sun Enterprise SyMON 2.x, Sun Management Center 2.x, or Sun Management Center 3.0 is installed on the prototype

machine, uninstall the SyMON or Sun Management Center software from the prototype machine. For SyMON or Sun Management Center software uninstall procedures, see the installation manual for the SyMON or Sun Management Center software. Do not save the configuration data from the previous version of Sun Management Center.

For detailed information about the JumpStart software, see *Solaris 9 9/04 Installation Guide*.

System Services Needed

The JumpStart software requires the following system services.

TABLE 6-1 System Services Required for the JumpStart Software

Service	Used for
Network File System (NFS) daemons <code>mountd</code> and <code>nfsd</code>	Sharing the Solaris operating system image files
<code>rarp</code>	IP address discovery
<code>bootp</code>	Host definition and location of shared file systems
<code>tftp</code>	Transfer of the Solaris initial boot kernel from the boot server to the install client

JumpStart Process Overview

Deployment of the Sun Management Center 3.6 base agent is performed by the JumpStart finish script, which is run on the install clients. After JumpStart installs the specified Solaris operating environment, the JumpStart finish script installs the base agent on the install client based on the contents of the Sun Management Center install response file.

The finish script also prepares the install client to set up the base agent after the install client reboots, based on the contents of the Sun Management Center setup response file.

The Sun Management Center response files are generated during the Sun Management Center 3.6 command-line installation and setup process on a separate or *prototype* system. The response files are then copied to the JumpStart profile directory. If needed, you can manually create the install and setup response files directly in the JumpStart profile directory.

JumpStart mounts the install client's file systems on the `/a` partition. The JumpStart finish script then installs the Sun Management Center base agent by running the Sun Management Center command `es-inst -R /a -T /a/target-directory`, where *target-directory* is the name of the directory on the install client in which the agent is installed. For information about the `es-inst` command and parameters, see [“es-inst Options” on page 217](#)

The finish script also creates an `rc3.d` file that runs after the install client reboots. The `rc3.d` file sets up the Sun Management Center base agent using the setup response file. When the base agent is set up, the `rc3.d` file is deleted. Output from the finish script is stored in `/var/sadm/system/logs/finish.log`.

Security Considerations for Finish Scripts

During Sun Management Center setup, you provided a password to generate the security key, and you provided an SNMP community string. To ensure security, the security key and community string are not stored in the Sun Management Center setup response file.

To successfully install and set up the Sun Management Center base agent on an install client, you must provide the same password that was used to generate the security key in [“Setting Up Sun Management Center” on page 33, Step b](#). You must also provide the same SNMP community string that you specified in [“Setting Up Sun Management Center” on page 33, Step c](#). This can be performed using either of the following two methods.

- Hard-code the password seed and community string in the JumpStart finish script.

This method presents a security risk because the security password seed and the community string are visible in the finish script. The security risk can be reduced, but not eliminated, by setting the finish script file permission to 400.

- Configure the JumpStart finish script so that the password seed and community string are manually entered on the install client during base agent setup.

The finish script can be configured to prompt for the security password seed and SNMP community string responses on the install client. The answers are stored as variables in a temporary finish script. When the install client is rebooted, the `rc3.d` script executes the temporary finish script, and then restores the original finish script.

This method requires you to manually enter the security password seed and community string at each install client.



Caution – This method does not validate the password seed or the community string. Communication between the agent and server will fail if you enter the wrong password seed or community string. If base agent setup fails on any install client, or if the agent fails to communicate with the Sun Management Center server, you have to run `es-setup -F` individually on each install client.

Examples of JumpStart finish scripts for both methods are provided in [“To Create the JumpStart Finish Script” on page 141](#).

JumpStart Configuration and Use

The following list summarizes the major steps required to set up the JumpStart software and install the Solaris operating environment, and the Sun Management Center base agent, on one or more install clients.

- Create the JumpStart install and profile servers.
- Create the Sun Management Center 3.6 base agent image on the JumpStart install server.
- Generate the Sun Management Center 3.6 install and setup response files.
- Create the JumpStart profiles.
- Create the JumpStart finish scripts for Sun Management Center.
- Create the JumpStart rules file.
- Validate the JumpStart files.
- Add install client information to the JumpStart server.

When all of the above steps have been completed, you can use the JumpStart server to perform a fresh Solaris operating environment and Sun Management Center base agent install on one or more install clients.

The procedures in this section assume the following situation:

- The machine `bootserver01` has been configured as a boot server, and is to be used as the JumpStart boot server, install server, and profile server. Machine `bootserver01` has already been configured as the boot server.
- You are using `/export/home` as the base directory for all JumpStart files.

Note – You can specify any file system that has sufficient space for the Solaris operating environment install image, and for the Sun Management Center base agent install image. The file system should have a minimum of 500 Mbytes of free space.

If you have decided to use a different directory for the JumpStart base directory, replace `/export/home` in the following procedures with the name of the directory you have chosen for the JumpStart base directory.

- You have selected Solaris version 8 for JumpStart installations.

If you are using Solaris version 9, replace `Solaris_9` with `Solaris_8` where appropriate in the following sections.

- You have chosen the default location of `/opt` for Sun Management Center base agent installation.

▼ To Create the JumpStart Install Server and Profile Directory

Steps 1. Create the JumpStart install server and Solaris operating environment image.

- a. Log in as root on the machine you want to use as the JumpStart install server.
- b. Insert the Solaris installation CD 1 of 2 in your CD-ROM drive.
- c. Go to the `Tools` directory on the CD.

```
# cd /<DiskMountDir>/Solaris_2.8/Tools
```

- d. Create the Solaris operating environment installation image.

Type the command `./setup_install_server /install-server-directory`, where `install-server-directory` is the directory that is to be used to serve the install images. For example:

```
# ./setup_install_server /export/home/JumpStart/Solaris_8
Verifying target directory...
Calculating the required disk space for the Solaris_8 product
Copying the CD image to disk...
Install Server setup complete
```

- e. **Optional: Add the Solaris operating environment supplemental products to the JumpStart install server.**

Insert the Solaris installation CD 2 of 2 in your CD-ROM drive, and go to the `Tools` directory on the CD.

Type the command `./add_to_install_server /install-server-directory`, where `install-server-directory` is the directory that is to be used to serve the install images. For example:

```
# cd /<DiskMountDir>/s0/Solaris_8/Tools
# ./add_to_install_server /export/home/JumpStart/Solaris_8
```

2. Create the JumpStart profile directory on the server.

```
# mkdir /export/home/JumpStart/jumpstart
```

3. Insert the Solaris installation CD 1 of 2 in your CD-ROM drive.
4. Copy the JumpStart samples from the CD directory `Solaris_2.8/Misc/jumpstart_sample` to the JumpStart profile directory `/export/home/JumpStart/jumpstart`. For example:


```
# cd /<DiskMountDir>/s0/Solaris_2.8/Misc
# cp -r jumpstart_sample/* /export/home/JumpStart/jumpstart
```
5. Stop the Network File System daemon `mountd`.


```
# /etc/init.d/nfs.server stop
```
6. Make the JumpStart directory NFS-shared.

The JumpStart directory must be NFS-shared so that the install clients can access the files on the JumpStart server. Add the following line to the `/etc/dfs/dfstab` file, then save and close the file.

```
share -F nfs -o ro,anon=0 /export/home/JumpStart
```
7. Start the Network File System daemon `mountd`.


```
# /etc/init.d/nfs.server start
```

▼ To Create the Base Agent Image on the JumpStart Install Server

- Steps**
1. Log in as root on the machine where you created the JumpStart install server.
 2. Insert the Sun Management Center 3.6 installation CD 1 of 2 in your CD-ROM drive.

Change to the directory `/<DiskMountDir>/sbin`.
 3. Type the command `./es-makeagent` to create the Sun Management Center base agent image.

You are prompted for the installation files source directory, and for the agent image target directory.

(SPARC) The source directory is `/<DiskMountDir>/image/sunOS/sparc`.

(x86) The source directory is `/<DiskMountDir>/image/sunOS/i386`

(Linux) The source directory is `/<DiskMountDir>/image/Linux`

The target directory is the directory on the JumpStart install server where the agent image is to be created, for example, `/export/home/JumpStart/AgentImage`.

Note – If the target directory that you specify does not exist, you are asked whether you want to create the directory. Type **y** to create the directory.

Example:

```
# ./es-makeagent
Installation files source directory: /<DiskMountDir>/image
Please enter the target directory: /export/home/JumpStart/AgentImage
```

Note – The image creation process can take over half an hour to complete.

4. Exclude add-on agents.

If you do not want to include the add-on agent components, rename the agent-image Addons directory.

```
# cd /export/home/JumpStart/AgentImage/disk1/image
# ls -p
Addons/      PE/          Patches/    Webserver/  db/
# mv Addons Addons-temp
```

▼ To Generate the Sun Management Center 3.6 Install and Setup Response Files

- Steps**
1. **Select a machine on which to install and set up the Sun Management Center base agent, and log in as root.**

This is the prototype machine.

Tip – Select a machine on which Sun Management Center has not been installed. If such a machine is not available, uninstall the SyMON or Sun Management Center software from the prototype machine as directed by the installation manual for the SyMON or Sun Management Center software. Do not save the configuration data from the previous version of Sun Management Center.

2. **Insert the Sun Management Center 3.6 installation CD 1 of 2 in your CD-ROM drive.**

Change to the directory /<DiskMountDir>/sbin.

3. **Create a directory on the machine in which to store the Sun Management Center install and setup response files.**

For example:

```
# mkdir /response-files
```

4. **Generate the Sun Management Center Install Response file.**

To generate the install response file, you must install the base agent using the command format `./es-inst -C /response-file-dir/install-response-file.cfg` where:

- *response-file-dir* is the directory that you created in which to store the response files
- *install-response-file* is the name of the response file

For example:

```
# ./es-inst -C /response-files/install.cfg
```

You are prompted for the directory in which to install Sun Management Center.

a. **Provide the name of the directory in which to install Sun Management Center**

You are prompted for the target directory. The default location is `/opt`.

Sun Management Center software can be installed in any location on your system where the minimum required disk space is available. If you want to install to a directory other than `/opt`, type the directory name.

Tip – The command `df -ak` lists the used space and free space for each file system on the machine.

You are asked whether you want to install either the production environment or the developer environment.

b. **Type 1 to install the production environment and press Return.**

Caution – Do not select (2) Developer Environment (DE). Option 2 installs the entire Sun Management Center base product.

You are prompted to select the Sun Management Center components that you want to install.

c. **Select only the agent component.**

Type `n` when prompted to install the server component.

Type `y` when prompted to install the agent component.



Type **n** when prompted to install the console component.

```
3 component(s) are available for your selection:
Do you want to install the Server component (y|n|q) n
Do you want to install the Agent component (y|n|q) y
Do you want to install the Console component (y|n|q) n
```

The install process checks for add-on components, and then prompts you to select add-ons.

d. Do not select any add-on components for installation.

Type **n** when prompted to select each add-on.

```
Select the products you want to install:
Advanced System Monitoring (y|n|q) n
Service Availability Manager (y|n|q) n
Performance Reporting Manager (y|n|q) n
Sun Fire Platform Administration (y|n|q) n
Monitoring and Management of A5x00 and T3 devices (y|n|q) n
System Reliability Manager (y|n|q) n
Workgroup Server (y|n|q) n
```

You are asked whether you want to proceed. Type **y** to continue.

e. Check disk space.

The installation process checks whether there is enough disk space to install the Sun Management Center base agent.

- If there is enough disk space, the base agent is installed.
- If there is not enough disk space, you are asked to provide an alternate file system. The amount of space that is available and the amount of space that is needed are displayed.

Tip – In a terminal window on the machine where you are installing the Sun Management Center agent, type **df -ak** to list the amount of used and free space for each file system on the machine.

When the agent installation completes, you are asked whether you want to run setup.



Caution – Do not run setup. Type **n** to exit. Running setup from within the install process will not create the Sun Management Center setup response file needed by the JumpStart finish script.

5. **Go to the directory `/opt/SUNWsymon/sbin`.**

If you installed Sun Management Center in a different location, go to the `/install-dir/SUNWsymon/sbin` directory, where *install-dir* is the directory you specified in [Step 4](#).

6. **Generate the Sun Management Center 3.6 setup response file.**

To generate the Sun Management Center setup response file, you must set up the base agent using the command format `./es-setup -C /response-file-dir/setup-response-file.cfg` where:

- *response-file-dir* is the directory that you created in which to store the response files
- *setup-response-file* is the name of the response file

For example:

```
# ./es-setup -C /response-files/setup.cfg
```

You are prompted to provide a seed for security key generation,

a. **Generate the security keys.**

An encrypted security key is needed for communications between all Sun Management Center processes. The key is generated based on the password seed that you provide. The seed must be between one and eight characters long, and contain no spaces. Entries that are greater than eight characters are truncated to eight characters.



Caution – You must ensure that you use the same security seed for all the machines that you install in a single server context.

Type the same password seed that you provided during Sun Management Center server setup in [Step b](#) in “[Setting Up Sun Management Center](#)” on [page 33](#).

Type the password seed again when prompted.

Note – To ensure security, the password seed that you provide is not stored in the Sun Management Center setup response file. You can either hard-code the password seed in the JumpStart finish script, or configure the finish script so that the install client prompts for the password seed when the finish script runs on the install client. Both methods of specifying the password seed are provided in “[To Create the JumpStart Finish Script](#)” on [page 141](#).

You are prompted for the SNMPv1 community string.

b. Specify the SNMPv1 community security string.

An SNMPv1 community string is required for security, and by default is set to `public`. For additional security, a customized string can be specified.



Caution – You must ensure that you use the same SNMPv1 community string on all the machines that you install in a single server context.

Provide the same community string that you provided during Sun Management Center server setup in [Step c](#) in “[Setting Up Sun Management Center](#)” on page 33.

- If you used the default community string of `public`, press Return when prompted to submit the SNMPv1 community string.
- If you specified a custom community text string, type the same community string that you provided during Sun Management Center server setup.

Note – To ensure security, the community string that you provide is not stored in the Sun Management Center setup response file. You can either hard-code the community string in the JumpStart finish script, or configure the finish script so that the install client prompts for the community string when the finish script runs on the install client. Both methods of specifying the community string are provided in “[To Create the JumpStart Finish Script](#)” on page 141.

You are prompted for the Sun Management Center server host name.

c. Specify the Sun Management Center server host name.

Type the name of the machine on which the Sun Management Center server was installed.

The setup process checks whether the SNMP port is in use.

- If SNMP port 161 is not in use, you are asked whether you want to start the Sun Management Center agent. Go to [Step e](#).
- If SNMP port 161 is in use, you are prompted to assign an SNMP port number.

d. Resolve the SNMP port conflict.

Type the same port number that you provided during Sun Management Center server setup in [Step f](#) in “[Setting Up Sun Management Center](#)” on page 33.

e. Start the Sun Management Center agent.



Caution – If your network uses Network Address Translation (NAT), type **n** to exit setup without starting Sun Management Center. Use the `es-config` command-line utility described in [“To Enable NAT Support” on page 197](#) to configure the machine for NAT before you start Sun Management Center.

- If you want to start the Sun Management Center base agent now, type **y**.
The setup script starts the agent using `es-start -A`. See [“Starting Components Using es-start” on page 167](#) for information about `es-start`.
Also, see [“Starting the Console” on page 168](#) for instructions on how to start the Sun Management Center console.
- If you want to start Sun Management Center later, type **n**. See [Chapter 8](#) when you are ready to start the Sun Management Center agent on this machine.

7. Copy the install and setup response files to the JumpStart profile server.

As an example in the previous steps, the Sun Management Center install response file `install.cfg` was created on the prototype machine in the directory `/response-files`. The Sun Management Center setup response file `setup.cfg` was also created on the prototype machine in the directory `/response-files`.

Assume that your JumpStart profile server is named `bootserver01`, and the JumpStart profile directory on machine `bootserver01` is `/export/home/JumpStart/jumpstart`. Also assume that you have enabled write-access to the JumpStart profile directory from the prototype machine. You would then copy the response files from the prototype machine to the JumpStart profiles directory on the JumpStart machine. For example:

```
# cd /response-files
# cp install.cfg /net/bootserver01/export/home/JumpStart/jumpstart
# cp setup.cfg /net/bootserver01/export/home/JumpStart/jumpstart
```

8. Log in as root on the machine where you created the JumpStart profile directory.

9. Go to the JumpStart profile directory that you created in Step 2, in [“To Create the JumpStart Install Server and Profile Directory” on page 131](#).

10. Edit the Sun Management Center install response file.

You must edit the install response file so that it can be used by JumpStart. The install response file is the file name you specified in [Step 4](#). Make the following changes to the install response file:

- Change the `SOURCE_DIRECTORY` value to `/a/mnt/disk1/image`. The `/a/mnt/disk1/image` corresponds to the `$MNTDIR` value specified in the JumpStart finish script.
- Change the `TARGET_DIRECTORY` value to `/a/target_directory`, where `target_directory` is the directory on each install client where the Sun Management Center base agent is to be installed.

- Change the value of the `SETUP_NOW` parameter to zero. Setting the value of the `SETUP_NOW` parameter to zero ensures that the Sun Management Center setup does not automatically run on each install client when the Sun Management Center base agent has been installed.

The following sample shows a basic Sun Management Center install response file after edits have been completed.

```
SUNMC_VERSION=3.6
ENVIRONMENT=1
SOURCE_DIRECTORY=/a/mnt/disk1/image
TARGET_DIRECTORY=/a/opt
OSVERS=8
PRTOUT= Sun Microsystems sun4u PCI (UltraSPARC-II 450MHz)
LAYER.SERVER=0
LAYER.AGENT=1
LAYER.CONSOLE=0
SETUP_NOW=0
```

The value of the `PRTOUT` parameter is not important because the base agent is platform independent. However, JumpStart requires this parameter to be present. Do not delete the `PRTOUT` parameter.

11. Edit the Sun Management Center setup response file.

You must edit the setup response file so that it can be used by JumpStart. The setup response file is the file name that you specified in [Step 6](#). Make the following changes to the setup response file if needed:

- Make sure that the server name specified by the `SUNMC_SERVER` parameter is the name of the Sun Management Center 3.6 server machine.
- Make sure that the value of the `START_SUNMC` parameter is set to 1 (one). Setting the value of the `START_SUNMC` parameter to 1 ensures that the Sun Management Center base agent is started after it has been set up.
- Make sure that the `agent_OPTIONAL_PORT` parameter is present, and that the assigned value is either a valid port number, or the text string `DEFAULT`.
- Make sure that all of the parameters in the sample setup response file shown below are present.

The following examples show a Sun Management Center setup response file before and after JumpStart edits have been applied. In both examples, `bootserver01` is the name of the Sun Management Center server machine.

Example 6–1 Setup Response File Before JumpStart Edits Are Applied

```
SUNMC_SERVER=bootserver01
agent_OPTIONAL_PORT=1161
START_SUNMC=1
```

Example 6–2 Setup Response File After JumpStart Edits Are Applied

```
DISABLE_SNMPDX_DAEMON=1
STOP_SNMPDX=1
```

```
SUNMC_SERVER=bootserver01
agent_OPTIONAL_PORT=1161
START_SUNMC=1
```

In this example, the line `DISABLE_SNMPDX=1` disables the SNMP daemon. The line `STOP_SNMPDX=1` stops the SNMP daemon. The line `SUNMC_SERVER=bootserver01` specifies that the base agent Sun Management Center server host is the machine named `bootserver01`. The line `agent_OPTIONAL_PORT=1161` assigns port 1161 to the agent. The line `START_SUNMC=1` starts the base agent when base agent setup is complete.

▼ To Create the JumpStart Profiles

- Steps**
1. Log in as root on the machine where you created the JumpStart profile directory.
 2. Go to the JumpStart profile directory that you created in Step 2, in “To Create the JumpStart Install Server and Profile Directory” on page 131.
 3. Create a JumpStart profile for each type of install client on which you will install the Sun Management Center base agent.

You can create a JumpStart profile either by copying an appropriate sample profile from the samples in the directory, or by using the following example as a template. Save each JumpStart profile that you create in the JumpStart profile server directory, and record the name of each profile you create.



Caution – Do not use a sample profile as the actual profile. Edit the profile to meet the JumpStart requirements, as described in “Creating a Profile” in Solaris 9 9/04 Installation Guide.

The following examples show sample JumpStart profiles. The first example shows a profile that is used for a fresh Solaris operating environment install. The second example shows a profile that is used for Solaris operating environment upgrade.

Example 6–3 Sample JumpStart Profile: Fresh Solaris Operating Environment Install

```
#
# all_9000_t0+swap
#
install_type      initial_install
system_type       standalone
partitioning      explicit
#
filesys           c0t0d0s1        2024    swap
filesys           c0t0d0s0        6120    /
```

```

filesys      c0t0d0s7      free    /export/home
#
cluster     SUNWCall
package     SUNWabe        delete
cluster     SUNWCapache    delete
cluster     SUNWCdhcp      delete
cluster     SUNWClux       delete
cluster     SUNWCfct       delete
cluster     SUNWCnet       delete
package     NSCPcom        delete

```

Example 6–4 Sample JumpStart Profile: Upgrade Solaris Operating Environment Install

```
install_type    upgrade
```

▼ To Create the JumpStart Finish Script

- Steps**
1. Log in as root on the machine where you created the JumpStart profile directory.
 2. Go to the JumpStart profile directory that you created in Step 2, in “To Create the JumpStart Install Server and Profile Directory” on page 131.
 3. Create the JumpStart finish script.

Review “Security Considerations for Finish Scripts” on page 129. Then, depending on your security requirements, use either of the following sample finish scripts as a guideline to create the finish script in the JumpStart profile directory.

The first example shows a finish script in which the password seed and community string are hard coded. The second example shows a finish script that will prompt for the password seed and community string.

Save your finish script with the sh extension, for example, base_agent_finish.sh.

Example 6–5 Sample Finish Script: Security Password Seed and Community String Hard Coded

```

#!/bin/sh
#
# Program type      : Unix bourne shell script
# Description       : Standard finish script for installing and
#                   setting up Sun Management Center core agent
#
#
#
ROOTDIR=${ROOTDIR:-/a}          # Root directory for new OS
MNTDIR=${ROOTDIR}/mnt

```

```

LOGDIR=${ROOTDIR}/var/tmp/sunmcfinish
SI_CONFIG_DIR=${SI_CONFIG_DIR:-/export/home/JumpStart/jumpstart}
INSTALL_RESP=${SI_CONFIG_DIR}/install.cfg
SETUP_RESP=${SI_CONFIG_DIR}/setup.cfg
#
#
# Begin Main Program
#
#
umask 022
mkdir -p $LOGDIR
#
# Copy the install and setup response file to target system
#
cp ${INSTALL_RESP} $LOGDIR
cp ${SETUP_RESP} $LOGDIR
#
# mount Sun Management Center image
#
mount -F nfs bootserver01:/export/home/JumpStart/AgentImage $MNTDIR
[ $? -ne 0 ] && exit 1
#
# run es-inst with -a -R -T and -A options
# skip the next line for Flash Archive based deployment
# Do not use the -T option if you have specified the TARGET_DIRECTORY
# tag in install.cfg
#
${MNTDIR}/disk1/sbin/es-inst -a -R /a -T /a/opt -A ${LOGDIR}/install.cfg
#
# Clean up any rc script with the same name if present
#
test -f ${ROOTDIR}/etc/rc3.d/S80SunMCJumpStart && \
rm -f ${ROOTDIR}/etc/rc3.d/S80SunMCJumpStart
rm -f /etc/init.d/SunMCJumpStart
#
# Place rc script in rc3.d and init.d to do setup
# Remember to access es-setup based on the target directory location
#
echo "Creating rc script..."
cat > ${ROOTDIR}/etc/rc3.d/S80SunMCJumpStart << EOF
#!/sbin/sh
#
rm /etc/rc3.d/S80SunMCJumpStart /etc/init.d/SunMCJumpStart
SECURITY_SEED=abc123
SNMPV1_STRING=private
export SECURITY_SEED SNMPV1_STRING
/opt/SUNWsymon/sbin/es-setup -e -A /var/tmp/sunmcfinish/setup.cfg
EOF
cp ${ROOTDIR}/etc/rc3.d/S80SunMCJumpStart \
  ${ROOTDIR}/etc/init.d/SunMCJumpStart
exit 0

```

Example 6-6 Sample Finish Script: Prompt for Security Password Seed and Community

```
#!/bin/sh
#
# Program type      : Unix bourne shell script
# Description       : Standard finish script for installing and
#                   setting up Sun Management Center core agent
#
#
#
ROOTDIR=${ROOTDIR:-/a}          # Root directory for new OS
MNTDIR=${ROOTDIR}/mnt
LOGDIR=${ROOTDIR}/var/tmp/sunmcfinish
SI_CONFIG_DIR=${SI_CONFIG_DIR:-/export/home/JumpStart/jumpstart}
INSTALL_RESP=${SI_CONFIG_DIR}/install.cfg
SETUP_RESP=${SI_CONFIG_DIR}/setup.cfg
#
#
# Begin Main Program
#
#
umask 022
mkdir -p $LOGDIR
#
# Copy the install and setup response file to target system
#
cp ${INSTALL_RESP} $LOGDIR
cp ${SETUP_RESP} $LOGDIR
#
# mount Sun Management Center image
#
mount -F nfs bootserver01:/export/home/JumpStart/AgentImage $MNTDIR
[ $? -ne 0 ] && exit 1
#
# Read secure inputs from user who invoked boot net - install
#
echo "Enter Security seed:"
read SECURITY_SEED
echo "Enter SNMP string:"
read SNMPV1_STRING
#
# run es-inst with -a -R -T and -A options
# skip the next line for Flash Archive based deployment
# Do not use the -T option if you have specified the TARGET_DIRECTORY
# tag in install.cfg
#
${MNTDIR}/disk1/sbin/es-inst -a -R /a -T /a/opt -A ${LOGDIR}/install.cfg
#
# create a temporary es-setup script to use the secure information
# read earlier
# Remember to access es-setup based on the target directory location
#
FILE2=/a/opt/SUNWsymon/sbin/es-setup
FILE=/a/opt/SUNWsymon/sbin/es-setup.jumpstart
```

```

mv $FILE2 $FILE
count='wc -l $FILE'
count='echo $count | cut -d' ' -f1'
ncount=$count
count_enter='expr $ncount - 3'
while [ $ncount -gt 0 ] ; do
    k='tail -$ncount $FILE | head -1'
    if [ $ncount -eq $count_enter ]
    then
        echo $k >> $FILE2
        echo "SECURITY_SEED=$SECURITY_SEED" >> $FILE2
        echo "SNMPV1_STRING=$SNMPV1_STRING" >> $FILE2
    else
        echo $k >> $FILE2
    fi
    ncount='expr $ncount - 1'
done
chmod +x $FILE2
#
# Clean up any rc script with the same name if present
#
test -f ${ROOTDIR}/etc/rc3.d/S80SunMCJumpStart && \
rm -f ${ROOTDIR}/etc/rc3.d/S80SunMCJumpStart \
rm -f /etc/init.d/SunMCJumpStart
#
# Place rc script in rc3.d and init.d to do setup and cleanup
# Remember to access es-setup based on the target directory location
#
echo "Creating rc script..."
cat > ${ROOTDIR}/etc/rc3.d/S80SunMCJumpStart << EOF
#!/sbin/sh
#
rm /etc/rc3.d/S80SunMCJumpStart /etc/init.d/SunMCJumpStart
/opt/SUNWsymon/sbin/es-setup -e -A /var/tmp/sunmcfinish/setup.cfg
mv /opt/SUNWsymon/sbin/es-setup.jumpstart /opt/SUNWsymon/sbin/es-setup
EOF
cp ${ROOTDIR}/etc/rc3.d/S80SunMCJumpStart \
${ROOTDIR}/etc/init.d/SunMCJumpStart
exit 0

```

▼ To Create the JumpStart Rules File

- Steps**
1. Log in as root on the machine where you created the JumpStart profile directory.
 2. Go to the JumpStart profile directory that you created in [Step 2](#), in “To Create the JumpStart Install Server and Profile Directory” on page 131.
 3. Create the JumpStart rules file.

Use the following example rules file as a template, and create the rules file in the JumpStart profile directory.

Example 6-7 Sample Rules File

```
#
# rule keywords and rule values  begin script  profile  finish  script
# -----
# This rule matches one system:
#
hostname bootserver01          -          basic_prof  base_agent_finish.sh

# This is a complex rule:
#
network 192.43.34.0 && ! model \
  SUNW,SPARCstation-20          -          net_prof    -

# This rule applies to all
# SUNW,SPARCstation-LX:
#
model SUNW,SPARCstation-LX      -          lx_prof     complete.sh

# Another complex rule:
#
network 193.144.2.0 && karch i86pc  init.sh    IA_prof    done.sh

#
# You can use system attributes like RAM size and architecture to
# classify targets:
#
memsize 16-32 && arch i386         -          prog_prof   -

# rules are matched top-down. If nothing matches, this rule will apply:
#
any                               -          generic_prof  -
```

▼ To Validate Your JumpStart Files

- Steps**
1. Log in as root on the machine where you created the JumpStart profile directory.
 2. Go to the JumpStart profile directory that you created in [Step 2](#), in “[To Create the JumpStart Install Server and Profile Directory](#)” on page 131.
 3. Type `./check` to validate your JumpStart files.

```
# ./check
Validating rules...
Validating profile basic_prof...
Validating profile net_prof...
Validating profile lx_prof...
```

```

Validating profile IA_prof...
Validating profile prog_prof...
Validating profile any_machine...
The custom JumpStart configuration is ok.
# cat rules.ok
hostname bootserver01          -          basic_prof      base_agent_finish.sh
network 192.43.34.0 && ! model \
  SUNW,SPARCstation-20          -          net_prof         -
model SUNW,SPARCstation-LX      -          lx_prof          complete.sh
network 193.144.2.0 && karch i86pc  init.sh     IA_prof         done.sh
memsize 16-32 && arch i386       -          prog_prof        -
any -                            -          generic_prof     -

```

▼ To Add Install Client Information to the JumpStart Server

Steps 1. Log in as root on the JumpStart server.

2. Insert the Solaris installation CD 1 of 2 in your CD-ROM drive.

Go to the Tools directory on the CD.

```
# cd /<DiskMountDir>/s0/Solaris_2.8/Tools
```

3. Determine the system identification information for each install client.

The JumpStart server requires the following information about each install client.

- Name
- Ethernet address
- IP address
- Architecture

Log on to each install client, and use the arp and uname commands as follows to display the install client's Ethernet address, IP address, name, and architecture.

```
> arp clienthost
clienthost (111.222.123.124) at 8:0:80:e4:23:eb permanent published
> uname -a
SunOS clienthost 5.9 Generic_112233-01 sun4u sparc SUNW
```

In the above example, the clienthost install client Ethernet address is 8:0:80:e4:23:eb, the IP address is 111.222.123.124, and the architecture is sun4u.

4. Add the system identification information for each install client to the JumpStart server.

The add_install_client command is used to add the install client information to the JumpStart server as follows:

```
add_install_client \
-c JumpStart_profile_server:path_to_configuration_directory \
-s JumpStart_install_server:path_to_operating_environment_image \
```

```
-p JumpStart_profile_server:path_to_SYSIDCFG_file \
-e install_client_ethernet_address \
-i install_client_IP_address \
install_client_name install_client_architecture
```

For example, assume your systems are configured as follows.

- Machine `bootserver01` is your JumpStart boot server, profile server, and install server.
- The JumpStart configuration directory on `bootserver01` is `/export/home/JumpStart/jumpstart`.
- The JumpStart operating environment image directory on `bootserver01` is `/export/home/JumpStart/Solaris_8`.
- The system identification configuration file `sysidcfg` is located in the JumpStart configuration directory `/export/home/JumpStart/jumpstart`.
- The install client Ethernet address is `8:0:80:e4:23:eb`, and the IP address is `111.111.123.124`.
- The install client's name is `clienthost`, and the install client's architecture is `sun4u`.

You would then add the install client `clienthost` using the `add_install_client` command as follows.

```
# ./add_install_client -c bootserver01:/export/home/JumpStart/jumpstart \
-s bootserver01:/export/home/JumpStart/Solaris_9 \
-p bootserver01:/export/home/JumpStart/jumpstart \
-e 8:0:80:e4:23:eb -i 111.111.123.124 \
clienthost sun4u
Adding Ethernet number for clienthost to /etc/ethers
making /tftpboot
enabling tftp in /etc/inetd.conf
starting rarpd
starting bootparamd
updating /etc/bootparams
copying inetboot to /tftpboot
```

When you have finished adding install client system information to the JumpStart server, you can then use JumpStart to install the Solaris operating environment and the Sun Management Center base agent as described in the next step.

For further information about the `add_install_client` command and options, see the man page `add_install_client(1m)`.

5. Boot each install client.

- a. Logon as root on the client machine in single-user mode.
- b. At the `ok` prompt, type the command `boot net - install`.

For example:

```
{2} ok boot net - install
```

The client system boots from the JumpStart server. JumpStart installs the Solaris operating environment specified by the JumpStart profile assigned to the install client by the applicable rule in the rules file. When the operating environment has been installed, the Sun Management Center 3.6 base agent is installed. The install client then reboots.

When the install client reboot completes, the Sun Management Center base agent is set up according to the specifications of the finish script assigned to the install client by the applicable rule in the rules file. If you hard coded the security password seed and the SNMP community string in the finish script, base agent setup is automatic. If you chose not to hard code the password seed and community string in the finish script, you must respond to the base agent setup prompts on each install client to complete base agent setup.

Configuring Server and Agent on Multi-IP Machines

This section describes how to configure the Sun Management Center 3.6 server and agent on multi-IP machines.

Server Configuration

When installed on a system with multiple IP interfaces, the Sun Management Center 3.6 server is configured, by default, to support all agents on all of the IP interfaces.

The `esmultiip` command enables you to list, remove, or add an IP interface. The syntax of the `esmultiip` command is as follows:

```
esmultiip [-lh] | [ < -a | -d > Host-IP ]
```

The following table describes the `esmultiip` command parameters.

TABLE 6–2 esmultiip options

Option	Modifying Options	Definition
		Enable the multi-IP feature on the Sun Management Center server if more than one IP interface is present.

TABLE 6-2 esmultiip options (Continued)

Option	Modifying Options	Definition
-h		List the options for esmultiip
-l		List all of the active IP interfaces of the Sun Management Center server
-a	<i>Host-IP</i>	Add the host name corresponding to the IP address <i>Host-IP</i> to the list of active server IP interfaces
-d	<i>Host_IP</i>	Remove the host name corresponding to the IP address <i>Host-IP</i> from the list of active server IP interfaces

Note – The following procedures assume that the Sun Management Center server has been installed on the multi-IP machine in the directory `/opt`. If you installed the agent in a different directory, replace `/opt` with the name of the directory that you specified.

▼ To Add an IP Interface to the Sun Management Center Server

Steps 1. Log in as root on the server multi-IP machine.

2. List the current Sun Management Center active IP interfaces.

Type the command `/opt/SUNWsymon/sbin/esmultiip -l`. For example:

```
# /opt/SUNWsymon/sbin/esmultiip -l
Multi IP configured with active interfaces "10.1.2.111"
```

3. List all IP interfaces on the machine.

Type the command `ifconfig -a`. For example:

```
# ifconfig -a
lo0: flags=1000849<UP,LOOPBACK,RUNNING,MULTICAST,IPv4> mtu 8232 index 1
    inet 127.0.0.1 netmask ff000000
hme0: flags=1000843<UP,BROADCAST,RUNNING,MULTICAST,IPv4> mtu 1500 index 2
    inet 10.1.2.111 netmask ffffffff broadcast 10.1.2.255
    ether 8:0:20:a8:7a:c9
hme1: flags=1000843<UP,BROADCAST,RUNNING,MULTICAST,IPv4> mtu 1500 index 3
    inet 129.1.2.222 netmask ffffffff broadcast 129.199.199.255
    ether 8:0:20:a8:7a:c9
```

As shown by the above examples, only IP interface hme0 at IP address 10.1.2.111 is being used by the Sun Management Center server.

4. Add an IP interface.

Assume that you want to add the IP interface hme1 at IP address 129.1.2.222. You would then type the command `/opt/SUNWsymon/sbin/esmultiip -a 129.1.2.222`.

The IP interface is added to the list of active Sun Management Center server interfaces.

▼ To Remove an IP Interface From the Sun Management Center Server

Steps 1. **Log in as root on the server multi-IP machine.**

2. **List the current Sun Management Center active IP interfaces.**

Type the command `/opt/SUNWsymon/sbin/esmultiip -l`. For example:

```
# /opt/SUNWsymon/sbin/esmultiip -l
Multi IP configured with active interfaces "10.1.2.111 129.1.2.222"
```

3. **Remove an IP interface.**

Assume that you want to remove the IP interface hme1 at IP address 129.1.2.222. You would then type the command `/opt/SUNWsymon/sbin/esmultiip -d 129.1.2.222`.

The IP interface is removed from the list of active Sun Management Center server interfaces.

Agent Configuration

If the Sun Management Center 3.6 agent is configured to use one IP interface on a multi-IP machine, and another IP interface is configured for use by the server, then the Sun Management Center agent on the multi-IP machine cannot communicate with the Sun Management Center server.

The agent must be reconfigured to use the same IP interface as the server

Note – The following procedure assumes that only the Sun Management Center agent has been installed on the multi-IP machine in the directory `/opt`. If you installed the agent in a different directory, replace `/opt` with the name of the directory that you specified.

▼ To Configure the Sun Management Center Agent on a Multi-IP Machine

Steps 1. **Log in as root on the multi-IP agent machine.**

2. **Determine which IP address the agent is using.**

Type the command `uname -n` to display the machine name.

```
# uname -n
u60-01
```

The agent is configured to run on the IP address corresponding to the machine name reported by `uname -n`. In this example, the agent is configured to run on the IP interface assigned to machine name `u60-01`.

3. **Determine the IP interface addresses.**

Type the command `cat /etc/hosts` to display the machine name assigned to each IP interface.

For example:

```
# uname -n
SunOS u60-01-ip2 5.8 Generic_108528-07 sun4u sparc SUNW
# cat /etc/hosts
127.0.0.1      localhost
10.1.2.111    u60-01      loghost
10.2.3.222    u60-01-ip2
```

In the above examples, `uname -n` showed `u60-01`, and `u60-01` is assigned to the IP interface `10.1.2.111`.

If you want to configure the Sun Management Center agent to run on a different IP interface, reassign the agent to use the required IP interface as described in the following steps.

4. **Stop the agent if it is running.**

Type the command `/opt/SUNWsymon/sbin/es-stop -A`.

All Sun Management Center processes are stopped.

5. Change the machine name to the name assigned to the appropriate interface.

Assume that the agent uses IP interface 10.1.2.111, which is named `u60-01`. Also assume you want to reassign the agent to use IP interface 10.2.3.222, which is named `u60-01-ip2`.

You would then reassign to agent to IP interface 10.2.3.222 by typing the command `uname -S u60-01-ip2`.

6. Set up the agent.

You must set up the agent again to enable the agent to use the new IP interface assignment.

Type the command `/opt/SUNWsymon/sbin/es-setup -F`.

You are prompted for the security key seed.

a. Specify the Sun Management Center security key.

Type the same security seed password that you provided during Sun Management Center setup in “Setting Up Sun Management Center” on page 33, Step b. Type the password again to confirm.

You are prompted for the SNMPv1 community string.

b. Specify the SNMPv1 community string.

Type the same community string that you provided during Sun Management Center setup in “Setting Up Sun Management Center” on page 33, Step c. If you used the default value `public`, press Return.

You are informed that *server-host-name* appears to be configured as your Sun Management Center server, where *server-host-name* is the name of the machine where the server was installed.

- If the displayed server name is correct, type **y**.
- If the displayed server name is not correct, type **n**. You are prompted to provide the Sun Management Center host name.

Type the name of the machine where the server is installed.

The agent is set up to use the new IP address.

Note – If you installed any add-on agent components, you might be asked to set up the add-on components as well.

Agent configuration is now complete, and you can restart the agent.

7. Restart the agent.

Type the command `/opt/SUNWsymon/sbin/es-start -A`.

Installing Sun Management Center 3.6 on Microsoft Windows

Only the Sun Management Center console and the console components of some add-ons can be installed on Microsoft Windows. The Microsoft Windows machine must be accessible by your Solaris or UNIX network, and must have access to your network for the console to work.



Caution – Before you install Sun Management Center 3.6 on any Microsoft Windows platform, make sure that you have set the Java environment variables and path as described in [“Java Environment Variables and Path” on page 77](#). Installation will fail if JDK version 1.3.1, 1.4, or 1.4.1 has not been installed and configured.

Before you install Sun Management Center 3.6 on Microsoft Windows 98, make sure that you have set the minimum swap space and environment space as described in [“Microsoft Windows 98 Swap Space and Environment Space” on page 79](#).

▼ To Install Sun Management Center 3.6 on Microsoft Windows

- Steps**
1. **Log in as administrator, or as a user with administrator privileges.**
 2. **Run Windows Explorer.**
 3. **Review the README file.**

If you are installing from the CD, insert Sun Management Center disk 1 of 2 in the CD-ROM drive, and then use Windows Explorer to navigate to and open `/install/windows_install_readme.txt`.

If you are installing from the Sun Management Center cd-image, use Windows Explorer to navigate to and open `/net/machine-name/cd-imagedir/disk1/install/windows_install_readme.txt`.
 4. **Use the Windows Explorer to navigate to `/install/install.bat` and double-click the icon.**
 5. **The Welcome window appears.**

Ensure that you have the information listed, and then click Next.

The Specify the Installation Destination Directory window appears.

6. Specify the installation directory.

You are prompted for the directory in which to install Sun Management Center. The default location is `C:\Program Files\SUNWsymon`. The Sun Management Center 3.6 console can be installed in any location on your system where the minimum required disk space is available.

Click Next to accept the default of `C:\Program Files\SUNWsymon`, or browse to a directory name, select the directory, and then click Next.

- If the directory exists, the Select Add-on Products window appears.
- If the directory does not exist, you are informed that the directory does not exist, and asked "Create it now?".

Click Create. The window closes.

Click Next in the Specify the Installation Destination Directory window.

The Select Add-on Products window appears.

7. Select the add-ons that you want to install, and then click Next.

The Disk Space Check window appears.

- If there is enough free disk space to install Sun Management Center, the Confirmation window appears.
- If there is not enough free disk space, you are prompted to specify a different directory, or to browse to and select a different directory.

The disk space check is run again. If the directory does not have enough space, you are again prompted to specify a directory that contains enough free space. If the directory that you specified has sufficient space, the Confirmation window appears.

8. Confirm installation selections.

A list of your selections is displayed.

- Confirm the selections. If the list is correct, click Next to start installation of Sun Management Center.
- If the list is not correct, click Back to return to the Select Add-on Products window to select the products that you want to install.

The installation in progress screen appears.

9. Complete the installation process.

When the progress bar is approximately 50% completed, you are informed that Installation of CD 1 is complete, and instructed to insert the next CD.

Remove the first CD, and insert Sun Management Center disk 2 of 2. Wait for the CD-ROM drive to finish spinning, and then click Next.

When the installation process completes, a list of installed products is displayed. Click Close.

See Also This concludes the Microsoft Windows installation process. Setup and configuration is not required for the Sun Management Center console on Microsoft Windows systems. You can now run the Sun Management Center console as directed by [“To Start the Console on Microsoft Windows”](#) on page 169.

Sun Management Center Post-Installation Tasks

This chapter provides the instructions for post-installation tasks you can perform to complete your Sun Management Center 3.6 configuration and implementation.

This chapter discusses the following topics:

- [“Setting Up Users” on page 157](#)
- [“Stopping and Disabling the SNMP Daemons” on page 159](#)
- [“Installing Separately Released Add-on Products” on page 160](#)
- [“Sun Management Center Validation Tool” on page 162](#)

Setting Up Users

During Sun Management Center server setup, the file `/var/opt/SUNWsymon/cfg/esusers` is created.

Sun Management Center users are valid UNIX users whose login names are stored in the file `/var/opt/SUNWsymon/cfg/esusers`. All users listed in this file have general access privileges by default unless the user is given additional privileges, as described in [“To Assign a User to a Security Group” on page 158](#).

If a user login name is not in `/var/opt/SUNWsymon/cfg/esusers`, that user cannot log in to Sun Management Center. For a user to be able to access Sun Management Center, the user name must be added to the `/var/opt/SUNWsymon/cfg/esusers` file, as described in [“To Add Sun Management Center Users” on page 158](#).

Users must also be assigned a security level for access. Sun Management Center assigns users to specific security groups. Three groups are created by default during the installation process: `esops`, `esadm`, and `esdomadm`.

- `esops` is the group that is assigned to users who can effectively use the product and fine-tune its operation. These users cannot affect major configuration or architectural changes. The `esops` group has the greatest restriction of access privileges.
- `esadm` is the group that is assigned to users who can perform privileged operations, including the loading of modules and the configuration of managed objects and data properties. The `esadm` group has more access privileges than `esops`, but fewer access privileges than `esdomadm`.
- `esdomadm` is the group that is assigned to users who have domain administration privileges. These users can create top-level domains in a server context and assign privileges for other Sun Management Center users within these domains. This role is the highest-level role.

For further information about security groups and roles, see [“Users, Groups, and Roles Overview” on page 65](#). To find out how to assign a user to a specific Sun Management Center security group, see [“To Assign a User to a Security Group” on page 158](#). For further information about Sun Management Center security, see [“Security Recommendations” on page 65](#).

▼ To Add Sun Management Center Users

- Steps**
1. Log in as root (`su - root`) on the Sun Management Center server machine.
 2. Add the user name on a new line in the `/var/opt/SUNWsymon/cfg/esusers` file.
The user name that you add must be a valid UNIX user name.
 3. Save the file and exit the editor.

See Also The user can now log in to Sun Management Center as a general user with limited access privileges. To enable additional access privileges for the user, assign the user to a specific security group. For further information about security groups, see [“Users, Groups, and Roles Overview” on page 65](#).

▼ To Assign a User to a Security Group

- Steps**
1. Ensure that the user login name is in the `/var/opt/SUNWsymon/cfg/esusers` file.
 2. Log in as root on the Sun Management Center Server machine.
 3. In the `/etc/group` file, add the user to one of the following lines as applicable: `esadm`, `esops`, or `esdomadm`.
Separate each entry by a comma. For example, assume that you want to make the following assignments:

- sysadmin1 and syadmin2 to the domain administration group esdomadm
- admin1, admin2, and admin3 to the administration group esadm
- ops1 and ops2 to the operations group esops

The entries in the `/etc/group` file would then be:

```
esadm::1000:admin1,admin2,admin3
esdomadm::1001:sysadmin1,sysadmin2
esops::1002:ops1,ops2
```

See “Users, Groups, and Roles Overview” on page 65 for a thorough description of each of the security groups.

4. Save the file and exit the editor.

The user can now log in to Sun Management Center using the security privileges that you have assigned.

Stopping and Disabling the SNMP Daemons

The Sun Management Center agent uses User Datagram Protocol (UDP) port 161 by default to communicate with the Sun Management Center server. The Sun Management Center agent is a complete replacement and enhancement for the SNMP agent `snmpdx` and the Sun SNMP utility `mibissa`, which also use port 161 by default.

The SNMP agent `snmpdx` is the main component of Solstice Enterprise Agent technology. `snmpdx` and `mibissa` run as daemon processes and listen for SNMP requests on port 161.

Note – (On Solaris 10) If you use port 161, you are reminded to manually stop and disable the SNMP daemon, `SMA`.

If port 161 is in use during Sun Management Center setup, you are given the opportunity to specify a different port for the Sun Management Center agent and server, or to continue and use port 161. If you choose to use port 161, you are given the opportunity to stop and disable the SNMP agent daemon.



Caution – If you use port 161 and have chosen to manually stop and disable the SNMP daemon, Sun Management Center will not start until you stop all processes that use port 161.

The following procedure applies to any machine on which the Sun Management Center agent has been installed.

▼ To Stop and Disable `snmpdx` Manually

Steps 1. Log in as root.

2. Stop the `snmpdx` daemon by typing:

```
# /etc/rc3.d/S76snmpdx stop
```

3. Disable the `snmpdx` daemon by typing:

```
# mv /etc/rc3.d/S76snmpdx /etc/rc3.d/s76snmpdx
```

Note – A script whose name begins with an uppercase “S” automatically starts when the system reboots. A script whose name begins with a lowercase “s” is not run automatically.

Troubleshooting Your system might have other legacy SNMP agents or processes utilizing port 161. If Sun Management Center fails to start even though you have stopped and disabled `snmpdx`, view the agent `.log` file `/var/opt/SUNWsymon/log/agent.log` to see whether there is a port conflict.

▼ To Stop and Disable SMA Manually

Steps 1. Log in as root.

2. Stop and disable the SMA daemon by typing:

```
# /etc/init.d/init.sma stop
```

Installing Separately Released Add-on Products

Installing a separately released add-on product involves two steps:

- Installing the add-on product as directed by the documentation for the product.

- Setting up the add-on product by using either the Sun Management Center setup wizard `es-guisetup` or the command-line script `es-setup`.

Tip – You can install several add-ons, and then set up all of the add-ons by using the `es-guisetup` command.

▼ To Set Up an Add-on Product Using `es-guisetup`

Steps 1. **Log in as root on the Sun Management Center machine where the add-on is installed.**

2. **Go to the Sun Management Center `sbin` directory, for example:**

```
# cd /opt/SUNWsymon/sbin
```

If you installed Sun Management Center in a different directory than `/opt`, go to `/installdir/SUNWsymon/sbin`, where *installdir* is the directory that you specified.

3. **Run the `es-guisetup` script:**

```
# ./es-guisetup
```

The Welcome screen appears.

4. **Click Next.**

The Advanced Setup Options screen appears.

5. **Select Configure Add-ons and click Next.**

The Sun Management Center Core Product Setup Complete screen appears.

6. **Click Next.**

- If no add-ons have been set up, the add-ons are listed. You are informed that the listed add-ons will be set up. Click Next to start the setup process for the listed add-ons.
- If one or more add-ons have already been set up, those add-ons are listed. A list of add-ons that have not been set up is also displayed.

Select the add-on or add-ons that you want to set up, then click Next.

The setup screens for each selected add-on are presented in sequence. The Sun Management Center setup process prompts you for any information required by each selected add-on. Provide the requested information as needed. Refer to the add-on documentation for additional information for each add-on product that you selected.

If an add-on product setup failed, you are informed that the setup of the add-on product was not successful. You are then directed to see the log file for more details. The name of the log file is provided.

When the add-on setup process is complete, a list of the add-on components you installed and set up is displayed. You are prompted to click Next to start Sun Management Center, or to click Close to exit the setup process and start Sun Management Center later.

▼ To Set Up an Add-on Product Using `es-setup`

Steps 1. Log in as root on the Sun Management Center machine where the add-on is installed.

2. Go to the Sun Management Center `sbin` directory, for example:

```
# cd /opt/SUNWsymon/sbin
```

If you installed Sun Management Center in a different directory than `/opt`, go to `/installdir/SUNWsymon/sbin`, where *installdir* is the directory that you specified.

3. Determine the directory name of the add-on.

List the contents of the `installdir/SUNWsymon/addons` directory, for example:

```
# ls -p /opt/SUNWsymon/addons
AdvancedMonitoring/  PRM/                SystemManagement/  storage/
EServices/          SunfireSun4dConfigReader/  wgs/
```

4. Set up the add-on by typing `es-setup -p add-on-name`, where *add-on-name* is the directory name for the add-on. For example:

```
# ./es-setup -p SunfireSun4dConfigReader
```

The setup process is started for the specified add-on. When the add-on setup completes, you are asked whether you want to start the Sun Management Center agent and server processes.

- Type **y** to start the Sun Management Center agent and server.
- Type **n** to exit without starting the Sun Management Center agent and server.

Sun Management Center Validation Tool

The Sun Management Center validation tool `es-validate` checks and verifies installation and setup information after the software has been installed on your system. The tool is automatically installed when you install any of the base component layers.

`es-validate` provides the following information, which is based on the parameters you use:

- The version of the Sun Management Center base product installed on the local host
- The Sun Management Center base component layers installed on the host
- Whether the production environment or developer environment has been installed
- A list of all Sun Management Center base packages installed on the host
- A list of all Sun Management Center add-on packages and the version of each installed on the host
- The Sun Management Center base installation directory (BASEDIR)
- The Sun Management Center patch IDs that have been installed
- The Solaris operating environment version
- The disk space used by the Sun Management Center installation

The validation tool also checks functional aspects of your system, including the following items:

- Confirms whether the products installed on your system are compatible
- Checks whether the Sun Management Center base product and add-on products have been set up
- Checks whether the Sun Management Center database is functional
- Confirms whether the Sun Management Center Web server is running
- Displays all agents in the server context of the current Sun Management Center server, and also checks for agent connections in the server context
- Confirms whether the command-line interface is functional

`es-validate` Options

The syntax for the `es-validate` command is as follows:

```
es-validate [-s server [-r serverport] [-u user-name [-p password ]]] [-a agenthost [-b agentport] [-d]] [-c] [-o outfile]
```

The following table describes the `es-validate` parameters.

TABLE 7-1 `es-validate` Options

Option	Modifying Options	Description
-a	<i>agenthost</i>	Check connectivity with agent host machine <i>agenthost</i> .
-b	<i>agentport</i>	The SNMP port number associated with <i>agentport</i> .

TABLE 7-1 `es-validate` Options (Continued)

Option	Modifying Options	Description
-c		Show all the agents in the context of the Sun Management Center server specified with -s option.
-d		Show the version number of the agent on <i>agenthost</i> .
-o	<i>outfile</i>	Store the output of <code>es-validate</code> in file <i>outfile</i> . <i>outfile</i> should be an absolute file path. The default is an arbitrary file name in <code>/tmp</code> .
-p	<i>password</i>	The password for <code>-uuser-name</code> . If not specified, and <code>-uuser-name</code> is specified, you are prompted for the password.
-r	<i>serverport</i>	The Sun Management Center RMI port number. If not specified, port 2099 is used.
-s	<i>server</i>	The Sun Management Center server host name. If not specified, the current host is used.
-u	<i>user-name</i>	The user name used to connect with the Sun Management Center server. The <code>-u user name</code> parameter is mandatory for login checks.

Starting and Stopping Sun Management Center

This chapter provides the following procedures for starting and stopping Sun Management Center.

- “Commands Supported by the Linux Agent” on page 165
- “Starting Components on the Solaris Platform” on page 166
- “Starting the Console” on page 168
- “Stopping Components on the Solaris Platform” on page 169

Note – The procedures in this chapter assume that you installed Sun Management Center in the default file system `/opt`. If you installed Sun Management Center in a different location, replace `/opt` with the name of the file system you chose.

Commands Supported by the Linux Agent

The following commands are supported by the Linux agent:

- `es-start`
- `es-stop`
- `es-config`
- `es-dt`
- `es-inst` (remote installation is not supported)
- `es-uninst`
- `es-makeagent`
- `es-load-default`
- `es-platform`
- `es-run`

- es-trapdest
- es-validate
- es-setup

Starting Components on the Solaris Platform

This section describes how to start Sun Management Center components using the graphical user interface and the command-line script.

Note – On Solaris 10, if any service fails, Service Management Facility (SMF) will start that service. The only way to stop that service is to use `es-stop`.

Starting Components Using `es-guistart`

The graphical user interface wizard enables you to start specific Sun Management Center components as described by the following procedure.

▼ To Start Sun Management Center Using `es-guistart`

Steps 1. Log in as root on the machine on which you want to start Sun Management Center components.

2. Change to the `/opt/SUNWsymon/sbin` directory.

3. Run the start wizard by typing:

```
# ./es-guistart
```

The Select Components to Start screen appears.

Depending on the components installed on the machine, you might have one or more of the following options to select:

- Start Server Components
- Start Sun Management Center Agent
- Start Default Platform Agent
- Start Instance of Platform Agent

4. Select the components that you want to start and then click Next.

The Starting Components screen appears. The status of each component is listed.

Starting Components Using `es-start`

The `es-start` command-line script enables you to start specific Sun Management Center components. The syntax of the `es-start` command is as follows:

```
es-start -achlYAS [-y instance-name] [ -- args... ]
```

Note – `es-start` starts the Sun Management Server service through SMF.

The following table describes the `es-start` command parameters.

TABLE 8-1 `es-start` Options

Option	Modifying Options	Definition
-a		Start the agent
-c		Start the console
-c	--- -XmxNNm	Start the console with a default heap size of 64 Mbytes
-c	--- -p <i>port-number</i>	Start the console and override the default port with <i>port-number</i>
-c	<i>login-file</i>	Start the console and use <i>login-file</i> to supply the user name, password, host, and port
-n		
-h		List the options for <code>es-start</code>
-l		Start the platform agent
-y	<i>instance-name</i>	Start a new instance of the platform agent where <i>instance-name</i> is the name of the platform instance you provide
-Y		Start all instances of platform agents
-A		Start all components except the console
-S		Start the server and all the server subcomponents
-S	--- -XmxNNm	Start the server and all server subcomponents, arguments are passed to console or server when started

The *login-file* is used with the `-c` and `-n` options to specify a text file to retrieve login information. It has the following format:

```
username=user-name  
password=password  
serverhost=local-host  
serverport=port-number
```

Note – The user starting the console must be the same as the user name specified in the *login-file*.

The following examples show how to use `es-start` and its parameters.

To start all Sun Management Center processes, type:

```
# /opt/SUNWsymon/sbin/es-start -A
```

To start the console automatically, using a file to specify the login information, create a *login-file*. Then type:

```
# /opt/SUNWsymon/sbin/es-start -c -n login-file
```

To start the console, the server, and the agent, type:

```
# /opt/SUNWsymon/sbin/es-start -Ac
```

To specify the maximum console heap size when starting the console, use the `es-start -c` and `-X` parameters.

```
# /opt/SUNWsymon/sbin/es-start -c -- -Xmx100m
```

To specify a specific port when starting the console, use the `es-start -c` and `-p` parameters.

```
# /opt/SUNWsymon/sbin/es-start -c -- -p 2090
```

To specify the maximum server heap size when starting the server, use the `es-start -s` and `-X` parameters.

```
# es-start -S -- -Xmx100m
```

Starting the Console

This section describes how to start the Sun Management Center console on the Solaris platform and on Microsoft Windows.

▼ To Start the Console on the Solaris Platform

The same procedure applies on the Linux Platform also.

- Steps**
1. **Log in as an authorized Sun Management Center user on the Solaris machine where you have installed the Sun Management Center console.**

2. Change to the `/opt/SUNWsymon/sbin` directory.
3. Start the Sun Management Center console by typing:

```
# ./es-start - c &
```

The Sun Management Center Login screen appears.
4. Type your Sun Management Center user name in the Login ID field.
5. Type your Sun Management Center password in the Password field.
6. Type the name of the server where the Sun Management Center server layer is installed.
7. Click Login.
A connection is established to the Sun Management Center server, and your login is authenticated. The Sun Management Center Java console appears.

▼ To Start the Console on Microsoft Windows

- Steps**
1. Access the Sun Management Center Login window.
Double-click the Sun Management Center shortcut icon or choose Start → Programs → Sun Management Center → Console.

The Sun Management Center Login window appears. A command-prompt window also appears that displays the commands run by Sun Management Center.
 2. Type your Sun Management Center user name in the Login ID field.
 3. Type your Sun Management Center password in the Password field.
 4. Type the name of the server where the Sun Management Center server layer is installed.
 5. Click Login.
A connection is established to the Sun Management Center server, and your login is authenticated. The console appears.

Stopping Components on the Solaris Platform

This section describes how to stop Sun Management Center components using the graphical user interface or the command-line script.

Stopping Components Using `es-guistop`

The graphical user interface wizard enables you to stop specific Sun Management Center components as described in the following procedure.

▼ To Stop Sun Management Center Components Using `es-guistop`

Steps 1. Log in as root on the machine on which you want to stop Sun Management Center components.

2. Change to the `/opt/SUNWsymon/sbin` directory.

3. Run the stop wizard by typing:

```
# ./es-guistop
```

The Select Components to Stop screen appears.

Depending on the components installed on the machine, you might have one or more of the following options to select:

- Stop Server Components
- Stop Sun Management Center Agent
- Stop Default Platform Agent
- Stop Instance of Platform Agent

4. Select the components that you want to stop and then click Next.

The Stopping Components screen appears. The status of each component is listed.

Stopping Components Using `es-stop`

The `es-stop` command-line script enables you to stop specific Sun Management Center components. The syntax of the `es-stop` command is as follows:

```
es-stop -ahLYAS [-y instance-name]
```

Note – On Solaris 10, `es-stop` stops the services managed by SMF.

The following table describes the `es-stop` command parameters.

TABLE 8-2 `es-stop` Options

Option	Modifying Options	Definition
-a		Stop the Sun Management Center agent
-h		List the options for <code>es-stop</code>
-l		Stop the platform agent
-y	<i>instance-name</i>	Stop the platform agent instance named <i>instance-name</i>
-Y		Stop all instances of platform agents
-A		Stop all Sun Management Center components except the console
-S		Stop all Sun Management Center server and server subcomponents

The following examples show how to use `es-stop` and its parameters.

To stop all Sun Management Center processes, type:

```
# /opt/SUNWsymon/sbin/es-stop -A
```

To stop all Sun Management Center processes except the agent, type:

```
# /opt/SUNWsymon/sbin/es-stop -S
```


Sun Management Center Administration

This chapter provides the instructions for administrative tasks such as Sun Management Center backup, security key regeneration, and other tasks you can perform to resolve configuration problems with your Sun Management Center 3.6 installation.

This chapter discusses the following topics:

- “Sun Management Center Backup and Recovery” on page 173
- “Regenerating Security Keys” on page 178
- “SNMP Daemons and Legacy Agents” on page 180
- “Reconfiguring Port Addresses” on page 183
- “Assigning an Agent to a Different Server” on page 192
- “Using Sun Management Center With a Firewall” on page 196
- “Enabling Network Address Translation Support” on page 197

Note – The procedures in this chapter assume that you installed Sun Management Center in the default file system `/opt`. If you installed Sun Management Center in a different location, substitute `/opt` with the name of the file system you chose.

Sun Management Center Backup and Recovery

The `es-backup` command enables you to back up all base and add-on data in your database, and all of the configuration data in `/var/opt/SUNWsymon/cfg`. The `es-restore` command restores the database and configuration data from a previous backup.

Using es-backup

You should use `es-backup` to back up your database and configuration data as follows.

- On a scheduled, regular basis as part of standard maintenance
- Before performing a hardware or operating environment upgrade
- Before and after performing a Sun Management Center upgrade installation
- After a fresh Sun Management Center installation and setup

For more information on using the `es-backup` command to do online backups, see “Database Backup and Recovery” in *Sun Management Center 3.6 User’s Guide*.

The syntax of the `es-backup` command is as follows:

```
es-backup [ -h ] [ -c ] [-y] [ -d dir] [ -o ] [ -e ]
```

The following table describes the `es-backup` command parameters.

TABLE 9-1 `es-backup` Options

Option	Modifying Options	Description
-c		Perform cold backup.
-d	<i>dir</i>	Back up the database and configuration data to the directory <i>dir</i> .
-e		Report estimated backup size.
-h		List the options for <code>es-backup</code> .
-o		Perform an online backup.
-y		Perform a non-interactive backup. You will not be prompted to stop Sun Management Center processes, nor will you be prompted for a backup directory name. Note – If you do not specify a backup directory using the <code>--d</code> option, all database and configuration data is backed up to the directory <code>/var/opt/SUNWsymon/backup</code> .

To both minimize and prevent data loss, you should run `es-backup` on a routine basis to enable recovery of your most current data in the event of a system failure. You can create a `cron` entry for the `es-backup -y` script to run the script on a periodic basis. As part of the `cron` entry, you may also want to copy the contents of `/var/opt/SUNWsymon/backup` to an alternate directory.

Note – By default, a non-interactive backup overwrites the contents of `/var/opt/SUNWsymon/backup`. If you have previously performed a non-interactive backup of Sun Management Center data, and you want to save the previous backup, copy the contents of the directory `/var/opt/SUNWsymon/backup` to another location before running a non-interactive backup.

The following procedure assumes that you installed Sun Management Center in the default directory `/opt`. If you did not install Sun Management Center in `/opt`, replace `/opt` with the name of the directory you specified.

▼ To Manually Back Up Sun Management Center Data to the Default Directory

Steps 1. **Log in as root on the Sun Management Center server machine.**

2. **Stop all Sun Management Center processes.**

Type the command `/opt/SUNWsymon/es-stop -A` and press Return.

3. **Backup your Sun Management Center data.**

Type the command `/opt/SUNWsymon/es-backup` and press Return.

If any Sun Management Center processes are still running, you are notified that Sun Management Center must be shut down.

You are asked whether you want to proceed. Type `y` and press Return.

4. **Specify the backup directory.**

You are prompted for the directory path in which to store the backup. The default location `/var/opt/SUNWsymon/backup` is displayed.

- To accept the default backup directory `/var/opt/SUNWsymon/backup`, press Return.

If a prior backup has been performed using the default directory `/var/opt/SUNWsymon/backup`, you are asked whether to delete the old backups.

- To keep the old backups, type `n` to exit the backup process, then copy `/var/opt/SUNWsymon/backup` to a different directory.
- To overwrite the old backups, type `y`.

`es-backup` stops all running processes, and then backs up the database and configuration data to `/var/opt/SUNWsymon/backup`. When the backup is completed, `es-backup` starts all Sun Management Center processes.

- To specify a different backup directory, type the name of the directory and press Return.

For example:

```
# Enter full directory path to store the backup data files
[/var/opt/SUNWsymon/backup] : /backup-set-1
```

If the directory does not exist, you are asked whether you want to create the directory. Type **y** and press Return.

`es-backup` stops all running processes, and then backs up the database and configuration data to the directory you specified. When the backup is completed, `es-backup` starts all Sun Management Center processes.

5. Validate the backup.

Type the command `/opt/SUNWsymon/sbin/es-restore -c` and press Return.

You are prompted to enter the full directory path to the backup files. The default backup directory path `/var/opt/SUNWsymon/backup` is displayed.

- If you chose the default backup directory `/var/opt/SUNWsymon/backup`, press Return.
- If you specified a different backup directory, type the full path and name of the directory and press Return.

`es-restore` validates the data in the backup directory. You are informed whether the backup data is valid.

- If the backup is not valid, examine the backup log file `/var/opt/SUNWsymon/install/backup_host-name.date and time string.process-id` where:
 - *host-name* is the name of the server you used to create the backup
 - *date and time string* is the year, date, and time the backup was created
 - *process-id* is the process ID of the `es-backup` session that created the backup.
- If the backup is valid, copy the backup directory to a different directory for safe keeping.

The `es-backup` log file is

`/var/opt/SUNWsymon/install/backup_host-name.date and time string.process-id` where:

- *host-name* is the name of the server you used to perform the backup.
- *date and time string* is the year, date, and time the backup was run.
- *process-id* is the process ID of the `es-backup` session

Using `es-restore`

To restore your Sun Management Center database and configuration data, for example if your database has been corrupted due to a system failure, use the `es-restore` command.

The syntax of the `es-restore` command is as follows:

```
es-restore [-h] [-c] [ -d dir] [-y] [-f]
```

The following table describes the `es-restore` command parameters.

TABLE 9-2 `es-restore` Options

Option	Modifying Options	Description
-c		Verify the backup files only. Do not restore the data.
-d	<i>dir</i>	Restore the data using the backup files located in the directory <i>dir</i> .
-h		List the options for <code>es-restore</code> .
-f		Force database schema recreation.
-y		Use default answer.

The following procedure assumes that you installed Sun Management Center in the default directory `/opt`. If you did not install Sun Management Center in `/opt`, replace `/opt` with the name of the directory you specified.

▼ To Restore Sun Management Center Data Using the Default Backup Directory

- Steps**
- 1. Log in as root on the Sun Management Center server machine.**
 - 2. Stop all Sun Management Center processes.**
Type the command `/opt/SUNWsymon/es-stop -A` and press Return.
 - 3. Type the command `/opt/SUNWsymon/sbin/es-restore`.**
If any Sun Management Center processes are still running, you are notified that Sun Management Center must be shut down.

You are asked whether you want to proceed. Type `y` and press Return.
 - 4. Specify the backup directory.**
You are prompted for the directory path to the backup files. The default location `/var/opt/SUNWsymon/backup` is displayed.

- If you are restoring Sun Management Center from the default backup directory `/var/opt/SUNWsymon/backup`, press Return.
- If you are restoring Sun Management Center from a different backup directory, type the name of the directory and press Return.

All Sun Management Center processes are stopped. `es-restore` validates the backup data in the specified directory.

- If the backup data is corrupted, you are informed, and `es-restore` exits to the system prompt.

If you decide not to restore the Sun Management Center data from a different backup, and want to restart Sun Management Center, type the command `/opt/SUNWsymon/sbin/es-start -A` and press Return.

- If the backup data is valid, `es-restore` restores the database and configuration data from the specified directory.

When the restore is completed, `es-restore` restarts all Sun Management Center processes.

The `es-restore` log file is `/var/opt/SUNWsymon/install/restore_<host-name>.<date and time string>.<process-id>` where:

- *host-name* is the name of the server you used to perform the restore
- *date and time string* is the year, date, and time the restore was run
- *process-id* is the process ID of the `es-restore` session

Regenerating Security Keys

Security keys are used to validate communications between the Sun Management Center server and agent. The server and agent cannot communicate with each other if the server and agent have different security keys.

The Sun Management Center setup process generates the security keys for Sun Management Center components using the following default settings:

- Valid Sun Management Center users are `espublic` and `esmaster`
- Sun Management Center superuser is `esmaster`

The software uses an eight-character password string as a *seed* to make the generated key unique. During setup, you must create a seed. The same seed must be used for all server and agent setups in a given server context. For more information on server context, see “Access Control Definitions and Limitations” in *Sun Management Center 3.6 User’s Guide*.

Sun Management Center setup does not create UNIX accounts for the special users `espublic` and `esmaster`. You should not need to log into the Sun Management Center console using these user IDs. These IDs are reserved for internal communication between processes. However, some troubleshooting activities might require you to log in using one of these user IDs. If so, you have to create the user ID, and then assign a password using the usual UNIX commands `useradd` and `passwd`. The `esmaster` user ID bypasses normal permission checks, so use this ID with care. For normal operation, use an existing login account.

Setup provides an opportunity to specify an existing user as a Sun Management Center administrator. This user ID is added to the `esadm` and `esdomadm` groups as well as the `esusers` file. For more information on security and the Sun Management Center superuser, see Chapter 18, “Sun Management Center Security,” in *Sun Management Center 3.6 User’s Guide*.

The security keys for the components need to be regenerated if one or more of the following is true:

- UDP ports of any of the Sun Management Center agents change
- Host names or IP addresses of the Sun Management Center agent host change

Note – Changing the host name or the IP address of the Sun Management Center server is not supported.

▼ To Regenerate the Security Keys

Note – In these examples, *shared-secret* stands for a secret string of up to eight characters that is common to all machines in a server context. The string is required as an argument to the script `base-usm-seed.sh`. A default string (`maplesyr`) is provided by the software, but you can specify your own password. This secret string or password is used to generate keys for communication between processes.

The following procedure applies to machines on which the Sun Management Center server, agent, or both server and agent are installed.

- Steps**
1. Log in as root.
 2. Change to the `/opt/SUNWsymon/sbin` directory.
 3. Regenerate the security keys.
 - If you installed only the agent layer, type:

```
# ./es-run base-usm-seed.sh -s shared-secret -c agent -u public
```

- If you installed only the server layer, type:

```
# ./es-run base-usm-seed.sh -s shared-secret -c topology -u public
# ./es-run base-usm-seed.sh -s shared-secret -c trap event cfgserver servers
```
- If you installed both the agent and server layers on one host, type:

```
# ./es-run base-usm-seed.sh -s shared-secret -u public
```

4. Restart the Sun Management Center server.

For more information, see the *Sun Management Center 3.6 Software Installation Guide*.

SNMP Daemons and Legacy Agents

This section provides an overview of SNMP, and the procedure for configuring legacy SNMP agents as subagents of the Sun Management Center agent.

SNMP Overview

The Sun Management Center server uses SNMP to communicate with the Sun Management Center agents. SNMP also communicates with the other server components, such as the Topology manager, Configuration manager, Event manager, and Trap handler. By contrast, the Sun Management Center server uses remote method invocation (RMI) to communicate with the Sun Management Center consoles.

The SNMP port definitions for Sun Management Center components are defined in two files:

- The `/var/opt/SUNWsymon/cfg/domain-config.x` file exists in every machine running any Sun Management Center component
- The `/var/opt/SUNWsymon/cfg/server-config.x` file exists on machines that have the Sun Management Center server component installed

The `domain-config.x` file contains one configuration block for each of the SNMP-based Sun Management Center agents. Each configuration block contains at least one line that defines the port address for the corresponding agent. The default port definition for the Sun Management Center server is in the `server-config.x` file.

You can manually add hosts with Sun Management Center agents that use port addresses other than 161 to the administrative domain through the Create Topology Object window. Alternatively, you can discover these hosts automatically by specifying the port number in the discovery parameters. For more information on the Create Topology Object window, see Chapter 3, “Manually Adding Objects to the

Topology Database,” in *Sun Management Center 3.6 User’s Guide*. For more information on how hosts are discovered automatically, see Chapter 4, “Adding Objects to the Topology Database Using the Discovery Manager,” in *Sun Management Center 3.6 User’s Guide*. Because you can only specify one port number in addition to port 161, you should select an alternate port number and use that number for all agent installations.

Configuring a Legacy SNMP Agent as a Subagent of an Agent

A legacy SNMP agent is an SNMP agent that is not part of the Sun Management Center agent framework. You might need to configure one or more legacy agents as subagents of a Sun Management Center agent if you want to use the legacy agent with Sun Management Center.

Any legacy SNMP agent can be configured as a subagent of a Sun Management Center Agent provided that the following criteria are met:

- The legacy agent can run on a port other than 161
- The legacy agent configuration supports running that agent as a non-daemon process
- You have the legacy agent MIB definition file

The following procedure applies to machines on which the Sun Management Center server, agent, or both server and agent are installed.

▼ To Configure a Legacy SNMP Agent as a Subagent of an Agent

Steps 1. Log in as root.

2. If the file `/var/opt/SUNWsymon/cfg/subagent-registry-d.x` does not exist, copy the file from the `/opt/SUNWsymon/base/cfg` directory:

```
# cp /opt/SUNWsymon/base/cfg/subagent-registry-d.x /var/opt/SUNWsymon/cfg/
```

3. In the file `/var/opt/SUNWsymon/cfg/subagent-registry-d.x`, find the block that is similar to the following block:

```
# sa2 = {  
#   type           = legacy  
#   persist        = false  
#   snmpPort       = "20001"  
#   errorAction    = restart  
#   startCommand   = "/usr/lib/snmp/mibiisa -p %port"
```

```

# stopCommand      = "kill -9 %pid"
# pollInterval     = 60
# pollHoldoff      = 60
# oidTrees          = 1.3.6.1.2.1
# snmpVersion       = SNMPv1
# securityLevel     = noauth
# securityName      = espublic
# }

```

4. Remove the comment symbols (#) at the beginning of the line so that the code now looks like the following code.

```

sa2 = {
    type           = legacy
    persist         = false
    snmpPort        = "20001"
    errorAction     = restart
    startCommand    = "/usr/lib/snmp/mibiisa -p %port"
    stopCommand     = "kill -9 %pid"
    pollInterval    = 60
    pollHoldoff     = 60
    managedTrees    = "mib-2 sun"
    oidTrees        = 1.3.6.1.2.1
    snmpVersion     = SNMPv1
    securityLevel   = noauth
    securityName    = espublic
}

```

5. Modify the lines as follows:

- Change `sa2` to the unique subagent name for the agent.
- Set `type` to `legacy`.
- Set `persist` to `false` if the subagent is stopped when the Sun Management Center agent exits. If this value is `true`, then the Sun Management Center agent does not stop the subagent when the Sun Management Center agent exits.
- Set `snmpPort` to the UDP port number on which you want to run the subagent.
- Set `errorAction` to `restart`, `ignore`, or `kill`. If the `restart` option is used, the Sun Management Center agent tries to restart if the agent encounters an error when communicating with the subagent.
- Set `startCommand` to the mandatory command to start the subagent. This command should contain `%port`, which is replaced by the value that is given in `snmpPort`.
- Set `stopCommand` to the command to stop the process. `%pid` can represent the process ID (PID) of the subagent process.
- Set `pollInterval` to the time in seconds in which the Sun Management Center agent polls the subagent.
- Set `pollHoldoff` to the time in seconds after which the first poll is performed on the subagent after the Sun Management Center agent starts the subagent.
- Set `oidTrees` to a space-separated list of SNMP OIDs managed by the subagent.

- Set `snmpVersion` to either `SNMPv1`, `SNMPv2` or `SNMPv3`.
- Set `securityLevel` to either `priv`, `auth`, or `noauth`.
- Set `securityName` to the SNMPv1 community name or SNMPv2 security name you want to use.

For more details, refer to the descriptions in the `subagent-registry-d.x` file.

6. Stop and restart Sun Management Center to make the changes effective.

- a. **Type `/opt/SUNWsymon/sbin/es-stop -A` to stop Sun Management Center.**

Wait for all processes to stop successfully.

- b. **Type `/opt/SUNWsymon/sbin/es-start -A` to start Sun Management Center.**

Wait for all processes to start successfully.

See [Chapter 8](#) for further information.

Reconfiguring Port Addresses

This section describes how to configure Sun Management Center software when port addresses might conflict. See [Table 9-3](#) for a list of the default ports for each Sun Management Center component.

Note – The Sun Management Center setup process checks whether each default port is in use. If the port is not in use, the default port is assigned. If a port is in use, you are given the opportunity to specify a separate port. In either case, the port assignments are stored in the configuration files, as described in [“SNMP Overview” on page 180](#).

Default Ports

The default ports used by Sun Management Center components might be used by other processes already installed on the system. If you install Sun Management Center using the default port assignments, you might encounter port conflicts and be unable to start Sun Management Center. The Sun Management Center setup process checks the ports for each component. The process prompts you to either assign an alternate port or use the default port.

The following table lists the Sun Management Center components and the default port for each component. See [“To Determine Whether a Port Is Used” on page 184](#) to find out how to check whether a port is in use.

TABLE 9-3 Sun Management Center Default Port Addresses

Layer	Component	Default Port Number
Agent	Agent	161
Server	Trap handler	162
Server	Event manager	163
Server	Topology manager	164
Server	Configuration manager	165
Server	Platform	166
Advanced System Monitoring Add-on	System event and configuration tracking component <code>cstservice</code>	167
Server	Agent information caching component Metadata	168
Server	Server RMI	2099
Server	Database	2521
Server	Grouping	5600
Tomcat	Web server	8006
Server	Web server default port	8080
Server	Web server secure port	8443

▼ To Determine Whether a Port Is Used

- Step** ● In a terminal window, type `/bin/netstat -an | grep portnumber` where *portnumber* is the port number that you want to query. For example:

```
# /bin/netstat -an | grep 8443
#
```

- If the port is not in use, only the command-line prompt is returned as shown above.
- If the port is in reserved or in use, the status of the port is returned. For example:

```
# /bin/netstat -an | grep 1161
# *.*.1161 Idle
# /bin/netstat -an | grep 8080
# 172.16.0.0.8080 *.* 0 0 24576 0 LISTEN
```

where `172.16.0.0` is the IP address of the machine on which you entered the `netstat` command.

Reconfiguring Sun Management Center Ports

To reconfigure Sun Management Center ports, use the `es-config` command.

The following procedures provide examples of how to use the `es-config` command to reconfigure Sun Management Center port assignments.

▼ To Reconfigure the Agent SNMP Port

- Steps**
1. **Log in as root on the Sun Management Center server-layer machine.**
 2. **Locate an unused port.**
See [“To Determine Whether a Port Is Used”](#) on page 184.
 3. **Type `/opt/SUNWsymon/sbin/es-config -p agent`.**
`es-config` stops all Sun Management Center processes. The port numbers currently assigned to the Sun Management Center components are then displayed. The port number assigned to the agent is displayed next, and you are prompted to enter the port number.

```
# ./es-config -p agent
Following ports are occupied by Sun Management Center:
161,162,163,164,165,167,168,166,5600,2099,8080,8443.

Sun Management center agent component is presently using port:161
Hit RETURN key to continue with present configuration.
Enter the port number you would like to use for agent component
[ 1100 to 65535 ]:
```
 4. **Type the port number that you want to assign, or press Return to use the default 161 port assignment.**
You are asked whether you want to start the Sun Management Center components.
 5. **Type `y` to start the Sun Management Center components, or type `n` if you do not want to start the components.**

▼ To Reconfigure the Server RMI Port Address

- Steps**
1. **Log in as root on the Sun Management Center server-layer machine.**
 2. **Locate an unused port.**
See [“To Determine Whether a Port Is Used”](#) on page 184.
 3. **Type `/opt/SUNWsymon/sbin/es-config -p rmi`.**
`es-config` stops all Sun Management Center processes. The port numbers currently assigned to the Sun Management Center components are then displayed.

The port number assigned to the server is displayed next, and you are prompted to enter the port number. For example:

```
# ./es-config -p rmi
Following ports are occupied by Sun Management Center:
161,162,163,164,165,167,168,166,5600,2099,8080,8443.

Sun Management center agent component is presently using port:2099
Hit RETURN key to continue with present configuration.
Enter the port number you would like to use for rmi component
[ 1100 to 65535 ]:
```

4. **Type the port number that you want to assign, or press Return to use the default port assignment.**
You are asked whether you want to start the Sun Management Center components.
5. **Type y to start the Sun Management Center components, or type n if you do not want to start the components.**

Using es-config

The syntax for the es-config command is:

```
es-config [-Adhmnq] [-p sunmc_component] [-c sunmc_component:channel]
[-r | -o | -u usmuser] [-f filename] [-a option] [-P MinPort:MaxPort] [-W
webuser] [-M module] [-k lauser | -l lauser | -s]
```

The following table describes the es-config parameters.

TABLE 9-4 es-config Options

Option	Modifying Options	Description
-A		Configure all ports
-a	<i>option</i>	Setup database in archive log mode or no archive log mode.
-o		Reconfigure oracle memory.

TABLE 9-4 `es-config` Options (Continued)

Option	Modifying Options	Description
-P	<code>component:MinPort:MaxPort</code>	<p>Configure the probe mechanism port range where <i>MinPort</i> is the starting port number and <i>MaxPort</i> is the ending port number. The range of ports must be at least 20 for example, 1024:1044. The minimum specified ports for -P is 20. The ports are used by the probe mechanism to execute ad hoc commands for communication between the Sun Management Center server and agent or between server and console. Valid port numbers are 1100-65535.</p> <p>Valid values for <component> are <i>server</i> and <i>console</i>.</p> <p>Note – You must configure the port range to support communication between the Sun Management Center server and agent or between server and console through a firewall.</p>
-d		Restore all ports to the 3.6 default value. See Table 9-3 .
-c	<code>sunmc_component:channel</code>	<p>Enable or disable the component channels being logged. Valid Sun Management Center components for which channels can be controlled are <i>topology</i>, <i>cfgserver</i>, <i>event</i>, <i>cstservice</i>, <i>trap</i>, <i>metadata</i>, <i>agent</i>, <i>platform</i>, and <i>platform_instances</i>. Valid channels are <i>debug</i>, <i>info</i>, <i>error</i>, <i>status</i>, and <i>history</i>.</p>
-f	<code>file-name</code>	<p>Used with the <code>-r</code> option for reseeding. Reads the seed and community string from the specified file and seeds the esd component. The file has the format:</p> <pre>ES_SECURITY_SEED=<i>seed</i> ES_SNMPV1_STRING=<i>string</i></pre> <p>where <i>seed</i> is the seed you want to reseed with and <i>string</i> is the community string. The file should be owned by root and have read/write permissions for root only; otherwise the seed could be readable by unauthorized users.</p>
-h		List the <code>es-config</code> options.
-m		Configure module configuration propagation by adding a list of user names to the <code>es-mcp-users</code> configuration file.
-n		Enable Network Address Translation support.

TABLE 9-4 *es-config* Options (Continued)

Option	Modifying Options	Description
-p	<i>sunmc_component</i>	Configure port to be used by the Sun Management Center component <i>component-name</i> . Valid components are <i>topology</i> , <i>cfgserver</i> , <i>event</i> , <i>cstservice</i> , <i>trap</i> , <i>metadata</i> , <i>rmi</i> , <i>agent</i> , <i>grouping</i> , <i>HTTP</i> , <i>HTTPS</i> , <i>platform</i> , and <i>platform_instances</i> .
-q		Exit from script without starting the <i>esd</i> component. By default, the script tries to start the <i>esd</i> component before exiting.
-r		Re-seed product components. If <i>SUNWcry</i> or <i>SUNWcs1</i> package is installed, this option prompts you whether to enable SNMP encryption (privacy). For more information, see "SNMP Encryption (Privacy)" in <i>Sun Management Center 3.6 User's Guide</i>
-u	<i>username</i>	Add users to the User Security Model (USM) table locally on an SNMPv3 agent. <i><username></i> is the name of the SNMPv3 user to be added to the USM table. After entering the user name and pressing Return, you will be prompted to enter the passphrase (minimum of eight characters) and confirm it. This passphrase is used to generate the keys needed for performing SNMPv3 communication.
-W	<i>webuser</i>	Configure/change the specified user to start/stop the Web Server. Sun Management Center server uses <i>noaccess</i> as the default user to start/stop the Tomcat Web Server.
-M	<i>module</i>	Module name for local access user. Used in conjunction with <i>-k</i> , <i>-l</i> , <i>-s</i> .
-k	<i>lauser</i>	Delete the specified local access user. This is applicable for Service Management Facility (SMF), Module Configuration Propagation, and Solaris Container Manager modules.
-l	<i>lauser</i>	Add the specified local access user. This is applicable for Service Management Facility (SMF), Module Configuration Propagation, and Solaris Container Manager modules.
-s		Show all the local access users. This is applicable for Service Management Facility (SMF), Module Configuration Propagation, and Solaris Container Manager modules.

Multiple Trap Destinations

You can specify multiple secondary trap destinations for Sun Management Center agents with the `es-trapdest` command. *Secondary* trap destinations (zero or more) receive the same set of traps that are sent to the primary trap destination. Secondary trap destinations do not receive event traps. By default, all traps sent to secondary destinations use SNMPv2c with a community of `public`. The security level for secondary destinations is `noauth`.

Using the `es-trapdest` Command

Secondary trap destinations are managed with the `es-trapdest` command.

The syntax for the `es-trapdest` command is:

```
es-trapdest [-c] [-a host:port] [-v] [-u] [-f] [-d entrynum] [-l]
```

TABLE 9-5 `es-trapdest` Options

Option	Modifying Options	Description
-c		SunMC Component (agent, platform, etc.) Agent is the default component.
-l		List the currently specified secondary trap destinations.
-d	<i>entrynum</i>	Delete a currently specified secondary trap destination. <i>entrynum</i> is the number of the currently specified secondary trap destination to be deleted. <i>entrynum</i> must match the number listed using the -l option.
-a	<i>host:port</i>	Add a new secondary trap destination.
-v		SNMP Version (SNMPv1, SNMPv2c, SNMPv2u, or SNMPv3)

TABLE 9-5 *es-trapdest* Options (Continued)

Option	Modifying Options	Description
-u		SNMP User/Community
-f		Trap Filter. The list of OIDs or trap names to be sent to destination. If NOT is the first element, all traps are sent EXCEPT the ones listed.

You can also specify the following optional parameters when adding a new secondary trap destination with the *es-trapdest -a* command:

- v *version* Specify SNMP version: SNMPv1, SNMPv2c, SNMPv2u, or SNMPv3
- u *user* Specify the SNMP community or user name
- f *filter* Specify the trap filter

Trap Filter Specification

Trap filters are specified as a list of criteria, which can be either a series of numerical OID prefixes or a series of these mnemonic trap names:

- sunmcTraps
- snmpTraps
- coldStart
- warmStart
- linkDown
- linkUp
- authenticationFailure

The trap name *sunmcTraps* represents the OID prefix for all Sun Management Center enterprise-specific traps, and the trap name *snmpTraps* represents the OID prefix for all the standard traps defined in the SNMP RFCs.

Trap filters can be either positive or negative. A *positive* filter specifies which traps to send. A negative filter specifies which traps should *not* be sent. A *negative* filter is defined by specifying NOT as the first criterion.

For example, to forward only standard SNMP traps to the secondary trap destination, specify the filter as -f "snmpTraps".

To forward all traps *except* Sun Management Center enterprise-specific traps to the secondary trap destination, specify the filter as -f "NOT sunmcTraps".

Note – Filter specifications that contain spaces must be enclosed in quotation marks to prevent misinterpretation by the shell.

The following command adds `machine02:162` as a secondary trap destination that only receives `warmStart` and `coldStart` traps for the Sun Management Center agent:

```
es-trapdest -a machine02:162 -f "warmStart coldStart"
```

Platform Agent Instances

Each instance of a platform agent can have its own set of secondary trap destinations. To specify secondary trap destinations for a particular instance of a platform agent, use the `-c instance` option to the `es-trapdest` command, where *instance* is the name of the platform agent instance. If the `-c` is not specified as an argument to the `es-trapdest` command, the `es-trapdest` command uses the default value of agent, which manages the secondary trap destinations for the Sun Management Center agent component.

Registration Trap Configuration

You can configure the agent to send the registration trap at a custom interval. The parameter `agentRegisterHoldOff` controls the initial delay in sending the first registration trap. By default, the value of this parameter is set to 90 seconds. You can change this parameter value in the file `/var/opt/SUNWsymon/cfg/domain-config.x`. For example, to set the value to 120 in the file, you would type:

```
agent = {  
  agentServer = <myHostname>  
  ..  
  agentRegisterHoldOff = 120  
}
```

The value for this parameter should be between the minimum of 60 seconds and a maximum of 300 seconds.

If for some reason the initial trap is lost and is not received by the configuration server, the parameter `agentRegisterRetry` controls the interval for resending of the agent registration trap. The parameter has a default value of 300 seconds. If the registration trap is lost, the agent resends the registration trap at the retry interval until it is received by the configuration server.

You can change the parameter value from a minimum of 300 seconds to a maximum of 900 seconds. For example, to set the value to 450 in the file, you would type:

```
agent = {
  agentServer = <myHostname>
  ..
  agentRegisterRetry = 450
}
```

If you specify a value below the minimum, the system uses the minimum value (300 seconds). If you specify a value higher than the maximum, the system uses the maximum value (900 seconds). If you do not specify any values, the system uses the default value of 300 seconds.

Assigning an Agent to a Different Server

This section provides the instructions to assign an agent that is monitored by one Sun Management Center server to another Sun Management Center server.

In the following procedure, assume an agent is currently monitored from Sun Management Center server *Machine-A*, and you want to reassign the agent to Sun Management Center server *Machine-B*.

Reassigning an agent to a different server consists of two main steps as follows.

- Reassign the agent to a different server
- Clear the agent's cache entry from the original server

When an agent has been reassigned to a different server, a cached entry still exists in the original server for the agent. The cached entry must be cleared from the original server using the `es-servercontrol.sh` script to prevent access conflicts. If the cached entry is not cleared from the original server, the original server can still access the agent.

▼ To Assign an Agent to a Different Server

Steps 1. **Log in as root on the agent machine.**

2. **Reassign the agent to a different server**

To assign the agent to a different server, you must set up the agent using the command `es-setup -F`.

Type `/opt/SUNWsymon/sbin/es-setup -F`.

You are prompted for the security key seed.

3. **Enter the security seed.**

An encrypted security key is need for communications between all Sun Management Center processes. The key is generated based on the password you provide, which must be between one and eight characters long, and contain no spaces. Entries that are greater than eight characters are truncated to eight characters.

Make sure that you type the same security seed password that you provided during the original installation and setup process for [Step b](#) in “Setting Up Sun Management Center” on page 33.

a. **Type the password for the seed to generate the security keys.**

b. **Type the password again.**

You are prompted for the SNMPv1 community string.

4. **Specify the SNMPv1 community security string.**

The community string is used for SNMP security.

Make sure that you type the same community string that you provided during the original installation and setup process for [Step c](#) in “Setting Up Sun Management Center” on page 33.

You are informed that *Machine-A* is configured as your Sun Management Center server, where *Machine-A* is the actual name of the server to which the agent currently is assigned. For example:

```
# Machine-A appears to be configured as your Sun Management Center server.  
Is this correct (y|n|q)
```

Type **n**. You are prompted for the Sun Management Center server hostname.

5. Provide the hostname of the server to which you want to reassign the agent.

Type the name of the server. For example:

```
Machine-A appears to be configured as your Sun Management Center server.  
Is this correct (y|n|q) n  
Please enter the Sun Management Center Server Hostname: Machine-B
```

You are asked whether you want to start the Sun Management Center agent.

6. Start the agent.

- If you want to start Sun Management Center now, type **y**.

The setup script starts Sun Management Center using `es-start -A`. See [“Starting Components Using `es-start`” on page 167](#) for information about `es-start`.

Also, see [“Starting the Console” on page 168](#) for instructions on how to start the Sun Management Center console.

- If you want to start Sun Management Center later, type **n**. See [Chapter 8](#) when you are ready to start Sun Management Center.

7. Log in as root on the original server.

8. Type the command `/opt/SUNWsymon/base/sbin/es-servercontrol.sh`.

- If the `ESROOT` environment variable is set, you are prompted for the Sun Management Center server host name. Go to [Step 10](#).
- If the `ESROOT` environment variable is not set, you are notified and prompted for the `ESROOT` directory.

9. Specify the `ESROOT` directory.

The `ESROOT` environment variable specifies the location of the Sun Management Center `SUNWsymon` directory.

```
# The ESROOT environment variable is not set.  
Enter ESROOT [/opt/SUNWsymon]:
```

Press Return to accept the displayed default of `/opt/SUNWsymon`, or type the full path to the `SUNWsymon` directory.

10. Specify the Sun Management Center server host name.

You are prompted for the server host name.

```
Enter the hostname of the Sun Management Center server [Machine-A]:
```

Press Return to accept the displayed default hostname, or type the server hostname. The server hostname must be the name of the original server to which the agent was assigned.

You are prompted for the server port.

11. Specify the Sun Management Center server port.

The server port is the remote method invocation (RMI) port used by the Sun Management Center server. See [Table 9-3](#) for further information.

The current RMI port is displayed.

Enter the port of the Sun Management Center server [2099]:

Press Return to accept the displayed port, or type the port that is used for RMI.

You are prompted for the Sun Management Center superuser ID.

12. Specify the superuser ID.

The superuser ID is the administration user ID that you assigned during the original installation and setup process.

The current superuser ID is displayed.

Enter the Sun Management Center Superuser ID [esmaster]:

Press Return to accept the displayed ID, or type the administrator ID.

You are prompted for the superuser password.

13. Type the password.

A list of server control functions is displayed.

14. Clear the server cache.

Type **1** to select Clear the Server Context Cache. For example:

Select one of the following Server control functions:

- 0) View the Server Context Cache
- 1) Clear the Server Context Cache
- 2) Remove a host from the Server Context Cache
- 3) Remove a host:port from the Server Context Cache
- 4) View the SNMP OID (Finder) Cache
- 5) Clear the SNMP OID (Finder) Cache
- 6) Remove a host from the SNMP OID (Finder) Cache
- 7) Remove a host:port from the SNMP OID (Finder) Cache
- 8) Remove a host:port from the Cfgserver Engines Table
- 9) Exit

Please Enter Your Selection [9]:1

The server cache is cleared, and the server control list is displayed again. Type **9** to exit server control and return to the system prompt.

Using Sun Management Center With a Firewall

A *firewall* is a software or hardware device that controls access between networks. The firewall is located where one network connects to another network, for example, at the point where a corporate intranet connects to the global Internet. Due to increased security awareness, many organizations have implemented security policies within their networks using firewall technology. Because the Sun Management Center software uses a distributed architecture model, you must use the `es-config` to restrict the ports that Sun Management Center uses for firewalls.

The following procedures provide examples of how to use the `es-config` command to restrict the Sun Management Center firewall port assignments to the port range 6000 to 6150.

▼ To Restrict the Firewall Port Range

- Steps**
1. Log in as root on the Sun Management Center server-layer machine.
 2. Locate a range of unused ports.
See [“To Determine Whether a Port Is Used”](#) on page 184.
 3. Type `/opt/SUNWsymon/sbin/es-config -P 6000:6150`.

Note – The difference between the starting port number and the ending port number must be at least 100.

`es-config` stops all Sun Management Center processes. The port numbers currently assigned to the Sun Management Center components are then displayed. You are then informed that `/var/opt/SUNWsymon/cfg/domain-config.x` has been updated for the new configuration.

The Sun Management Center components are started.

Enabling Network Address Translation Support

If your network uses Network Address Translation (NAT), you must enable NAT support after you have installed and set up Sun Management Center 3.6. You cannot start Sun Management Center until you have enabled NAT support for each server, agent, and console machine in your network as described in the following procedure. See [Appendix D](#) for more information about NAT.

The following procedure assumes you installed Sun Management Center in the default directory `/opt`. If you did not install Sun Management Center in `/opt`, replace `/opt` with the name of the directory you specified.

▼ To Enable NAT Support

- Steps**
1. **Log in as root on the machine for which you want to enable Network Address Translation support.**
 2. **Type `/opt/SUNWsymon/sbin/es-config -n`.**
`es-config` stops all Sun Management Center processes. The port numbers currently assigned to the Sun Management Center components are then displayed.

You are asked to provide the host name for the machine. The machine name is displayed.
 3. **Provide the machine host name.**
 - If you are configuring the Sun Management Center server machine for NAT, press Return.
 - If you are configuring a Sun Management Center agent or console machine, type the name of the Sun Management Center server, and then press Return.

Note – Depending on the Sun Management Center 3.6 components installed on the machine, one or more informational messages could be displayed.

You are informed that Network Address Translation support is enabled for the machine. You are then asked whether you want to start the Sun Management Center components.

4. Determine whether to start Sun Management Center 3.6.



Caution – Do not start Sun Management Center until you have enabled NAT support for each machine in your network that uses Network Address Translation. The Sun Management Center agent will not run unless NAT support has been enabled for each machine.

Type **y** to start the Sun Management Center components, or type **n** if you do not want to start the components.

Integration With Other Enterprise Management Platforms

This chapter provides an overview of the integration of Sun Management Center with other management platforms. These platforms include HP OpenView Operations, BMC Patrol, Unicenter TNG, and Tivoli TME.

- [“HP OpenView Operations Integration” on page 199](#)
- [“BMC Patrol Integration” on page 201](#)
- [“Computer Associates Unicenter TNG Integration” on page 201](#)
- [“Tivoli TME Integration” on page 203](#)

HP OpenView Operations Integration

HP OpenView (HPOV) Operations, formerly known as VantagePoint Operations, is a distributed client/server software product for managing distributed environments. HPOV Operations is a centralized management console (server) that allows users to interact with agents running on host systems being managed.

Sun Management Center complements the features of HPOV Operations by providing in-depth monitoring and management of Sun products. Integration between HPOV Operations and Sun Management Center is accomplished through the HPOV agent and Sun Management Center server.

HPOV Integration Key Features

HPOV and Sun Management Center integration enables you to do the following tasks:

- Map Sun Management Center alarms to HPOV messages and the distribution of those alarms to the HPOV Operations management server
- Start the Sun Management Center console from the HPOV Application Bank

- Start the Sun Management Center Details Console for a chosen Sun Management Center managed node directly from the HPOV Application Bank
- Basic monitoring of the Sun Management Center server and Sun Management Center agent processes from the HPOV Operations management server

HPOV Integration Key Components

The key components for HPOV integration are as follows:

- HP OpenView VantagePoint Operations (VPO) Version A.05.xx or A.06.xx
- HP OpenView VantagePoint Operations (VPO) Integration Package Version A.02.00 for Sun Management Center
- Sun Management Center version 2.1.1, 3.0, 3.5, or 3.6

HPOV Integration Prerequisites

To integrate the Sun Management Center and HP OpenView Operations, the integration software must be installed on the HPOV server host and then distributed to all systems hosting Sun Management Center servers. This integration is facilitated by HPOV distribution capabilities.

The installation on the HPOV Operations server automatically adds a number of icons to the HPOV Application Bank, enabling operators to start the Sun Management Center console.

Event forwarding is performed through a mapper process, which connects to the Sun Management Center server and the HPOV agents.

HPOV Integration Supported Platforms

HPOV is supported on Solaris 2.6, Solaris 7, Solaris 8, and Solaris 9 releases.

HPOV Integration Additional Documentation

For more information on HPOV integration, see the *HP OpenView VantagePoint Operations - Integration for Sun Management Center Software User's Guide*

To access this document, go to http://ovweb.external.hp.com/lpe/doc_serv. Click IT/Operations for Sun Solaris, then download the document.

BMC Patrol Integration

For information about integrating BMC Patrol and Sun Management Center 3.6, contact BMC Direct Sales at (800) 841-2031, or email the BMC Field Support Center at FieldSupport@bmc.com.

Computer Associates Unicenter TNG Integration

The Unicenter TNG product provides network-monitoring functionality for a heterogeneous environment. Sun Management Center provides advanced capabilities and in-depth information for monitoring Sun products. An integration package from Sun provides a bridge between the two products. The integration of these two products provides Unicenter TNG users with superior management capabilities in environments that contain Sun products.

Unicenter TNG Integration Key Features

Unicenter TNG and Sun Management Center integration provides the following capabilities:

- Enables Unicenter TNG to discover Sun Management Center agents and their loaded modules, and present the agents and modules in the Unicenter TNG WorldView
- Enables agent status, agent alarms and agent module load and unload notifications to be forwarded from Sun Management Center to Unicenter TNG through traps
- Enables Unicenter TNG users to view Sun Management Center agent information by launching the Sun Management Center Host Details window from Unicenter TNG WorldView

Unicenter TNG Integration Key Components

The key components required to integrate Unicenter TNG and Sun Management Center are as follows:

- Computer Associates Unicenter TNG 2.4 and WorldView/DSM (Distributed State Machine) or Computer Associates Unicenter TNG 3.0 and WorldView/DSM.

- Sun Management Center Integration Package For Unicenter TNG which is available on the Sun Management Center CD. The Integration Package contains the following items:
 - Event Adaptor
 - Package for TNG WorldView class files
 - Package for Unicenter TNG DSM policy files
 - Package for launching Sun Management Center Details Window
- Sun Management Center version 2.1.1, 3.0, 3.5, or 3.6

Unicenter TNG Integration Prerequisites

The following software is required in order to integrate Unicenter TNG and Sun Management Center:

- Unicenter TNG version 2.4 or version 3.0 WorldView/DSM must be installed and running when installing the Unicenter TNG integration package.
- The Unicenter TNG integration package can be installed at the same time Sun Management Center is installed or as an add-on package. Sun Management Center versions 2.1, 2.1.1, 3.0, 3.5, and 3.6 support the Unicenter TNG integration package.
- The Sun Management Center server and the TNG Event Adaptor can be installed on different hosts. The TNG Event Adaptor must be installed on a host that already has the Sun Management Center console installed.
- The Unicenter TNG WorldView class files from the integration package must be installed on the same host as TNG WorldView.
- The Unicenter TNG DSM and Unicenter TNG must be on the same host as the Unicenter TNG DSM policy files from the integration package in order to be installed.

Unicenter TNG Integration Supported Platforms

The following platforms are supported:

- Sun Management Center agents: Solaris 2.6, Solaris 7, and Solaris 8 versions
- TNG Event Adaptor: Solaris 2.6, Solaris 7, and Solaris 8 versions
- TNG Integration Packages on TNG Server: Solaris 2.6, Solaris 7, and Solaris 8 versions

Starting the Adaptor in Command—Line Interface

You can run the Unicenter TNG adaptor without starting the graphical user interface. To start the adaptor in a command—line interface, use this syntax:

```
# SunMC_base_dir/SunMC-TNG/sbin/ea-start [ -h | help] [-f propertyfile \  
[ -u username ] ]
```

Note – The UNIX token (\) indicates the continuation of a command—line.

Here is an example of starting the CA Integration TNG Unicenter add-on in the command—line interface :

```
# /opt/SUNWsymon/SunMC-TNG/sbin/ea-start -f \  
/var/opt/SUNWsymon/SunMC-TNG/SunMCToTngAdaptorMain.cfg
```

Starting the Adapter in Graphical User Interface

To start the adaptor in the graphical user interface, use this syntax:

```
# SunMC_base_dir/SunMC-TNG/sbin/ea-start [-h help] [-ss serverhost] \  
[-sp serverport] [-ts TNG hostname, TNG hostname...] \  
[-tp TNG port] [-l log filepath] [-i pollinginterval] \  
[-u username]
```

Here is an example of starting the CA Integration TNG Unicenter add-on in the graphical user interface:

```
# /opt/SUNWsymon/SunMC-TNG/sbin/ea-start -ss sunmcserv -ts tngserv
```

Unicenter TNG Integration Additional Documentation

For more information on Unicenter TNG integration, see *Sun Management Center Integration Package User's Guide For Unicenter TNG*.

Tivoli TME Integration

Tivoli TME provides good general network monitoring functionality, and the Sun Management Center software provides excellent advanced capabilities and in-depth information for monitoring Sun products. Tivoli TME and Sun Management Center integration provides Tivoli administrators with significant additional functionality to manage networks that contain Sun products.

Tivoli TEC Integration Key Features

Tivoli TEC and Sun Management Center integration provides the following capabilities:

- Enables Tivoli TEC to acquire alarms from the Sun Management Center software based on preset filtering and formatting parameters
- Enables Tivoli TEC users to view Sun Management Center agent information by launching the Sun Management Center Host Details window from the Tivoli event console

Tivoli TEC Integration Key Components

The key components required to integrate Tivoli TEC and Sun Management Center are as follows:

- Tivoli TME 10
- Sun Management Center Tivoli TEC Adaptor, available on the Sun Management Center CD as an add-on product
- Sun Management Center 2.x or 3.x

Tivoli TEC Integration Prerequisites

The following software is required in order to integrate Tivoli TEC and Sun Management Center:

- Tivoli TME 10 FrameWork
- Tivoli TEC Server
- Tivoli TEC Console
- The Sun Management Center version 2.x or 3.x console residing on the Tivoli server on which the adapter is running

Tivoli TEC Supported Platforms

Solaris 2.6, Solaris 7, Solaris 8, Solaris 9 releases

Additional Documentation

Sun Management Center Tivoli TEC Adaptor Installation Guide

Uninstalling SyMON and Sun Management Center

This appendix provides the procedures for uninstalling previous versions of Solstice SyMON 1.x, Enterprise SyMON 2.x, and Sun Management Center 3.x.

This chapter discusses the following topics.

- “Uninstalling SyMON and Sun Management Center from the Solaris Platform” on page 205
- “Uninstalling Sun Management Center From the Microsoft Windows Platform” on page 211



Caution – If you want to preserve and use your existing SyMON or Sun Management Center configuration data, you must perform an upgrade install of Sun Management Center 3.6 as described in [Chapter 5](#).

Uninstalling SyMON and Sun Management Center from the Solaris Platform

If you have Solstice SyMON 1.x, Sun Enterprise SyMON 2.x, or Sun Management Center 3.x software installed on your system, and you do not want to preserve your configuration data, you must uninstall the SyMON or Sun Management Center software before you can install Sun Management Center 3.6 software.

Uninstalling Solstice SyMON 1.x or Enterprise SyMON 2.x

Use of this procedure deletes all Sun Management Center 1.x data, including any custom rules and alarms that you have defined. If you want to preserve your data for use with a later version of Sun Management Center, follow the procedures in [“Upgrading from Solstice SyMON 1.x and Sun Enterprise SyMON 2.x Software”](#) on page 92.

▼ To Uninstall Solstice SyMON 1.x or Enterprise SyMON 2.x

- Steps**
1. Log in as root on the machine where the SyMON server is installed.
 2. Uninstall the SyMON software as directed by the SyMON documentation.
 3. Ensure that all components have been uninstalled.

Type the following command to list all Sun Management Center packages:

```
# pkginfo -c symon
```

If any packages are listed, uninstall each package using the `pkgrm` command. For example:

```
# pkginfo -c symon
SUNWesse
# pkgrm SUNWesse
```

Uninstalling Sun Management Center 2.x

Use of this procedure deletes all Sun Management Center 2.x data, including any custom rules and alarms that you have defined. If you want to preserve your data and upgrade to Sun Management Center 3.6, follow the procedures in [“Upgrading From Sun Management Center 2.1 or 2.1.1”](#) on page 93.

▼ To Uninstall Sun Management Center 2.x

- Steps**
1. Log in as root on the machine where the Sun Management Center 2.x server is installed.
 2. Remove T3 device configuration information if T3 devices are present.
If you have not installed and set up the add-on Monitoring and Management of A5x00 and T3 Devices, skip this step. Go to [Step 3](#).

If you monitor and manage T3 storage devices using the Monitoring and Management of A5x00 and T3 Devices add-on, remove T3 device configuration information before you uninstall Sun Management Center. For instructions, see “Removing T3 Device Configuration If Present” on page 83 in Chapter 4.

3. Uninstall the Sun Management Center 2.x software.

Type the command `/opt/SUNWsymon/sbin/es-uninst`

Note – The Sun Management Center 2.x uninstall process removes the Sun Management Center 2.x software, but does not remove the Sun Management Center 2.x data.

4. Delete the Sun Management Center 2.x directories:

```
# rm -fr /opt/SUNWsymon
# rm -fr /var/opt/SUNWsymon
# rm -fr /etc/opt/SUNWsymon
```

5. Ensure that all components have been uninstalled.

Type the following command to list all Sun Management Center packages:

```
# pkginfo -c symon
```

If any packages are listed, uninstall each package using the `pkgrm` command. For example:

```
# pkginfo -c symon
SUNWesse
# pkgrm SUNWesse
```

Uninstalling Sun Management Center 3.0

The Sun Management Center 3.0 uninstall process provides you with the opportunity to save your Sun Management Center 3.0 configuration data. If you are going to upgrade to Sun Management Center 3.6, make sure that you save the Sun Management Center 3.0 configuration data when prompted.

▼ To Uninstall Sun Management Center 3.0

- Steps**
- 1. Log in as root on the machine where the Sun Management Center 3.0 server is installed.**
 - 2. Remove T3 device configuration information if T3 devices are present.**
If you have not installed and set up the add-on Monitoring and Management of A5x00 and T3 Devices, skip this step. Go to [Step 3](#).

If you monitor and manage T3 storage devices using the Monitoring and Management of A5x00 and T3 Devices add-on, remove T3 device configuration information before you uninstall Sun Management Center. For instructions, see “Removing T3 Device Configuration If Present” on page 83 in Chapter 4.

3. Uninstall Sun Management Center 3.0.

Type the following command:

```
# /opt/SUNWsymon/sbin/es-uninst
```

You are notified that the utility removes all of the Sun Management Center packages and asked whether you want to continue.

- Type **n** to cancel the uninstall process.
- Type **y** to continue.
You are asked if you want to preserve your existing data.

4. Choose whether to preserve your Sun Management Center 3.0 configuration data.

- If you do not want to preserve the existing Sun Management Center 3.0 data, type **n**. You are notified that the existing data will be removed.
- If you want to preserve the existing Sun Management Center 3.0 data and migrate the data to Sun Management Center 3.6, type **y**. You are notified that the existing data will not be removed.

Any Sun Management Center 3.0 processes that are currently running are stopped. The uninstall process then uninstalls the Sun Management Center 3.0 software.

Note – During the uninstall process, warning messages might be displayed saying that some packages depend on the packages being removed. Messages could also be displayed informing you that removal of a package was suspended and that intervention is required. You can safely ignore these messages because the uninstall process will remove the packages without your intervention.

The uninstall process exits to the system prompt when Sun Management Center 3.0 has been uninstalled.



Caution – If you want to upgrade to Sun Management Center 3.6, do not delete the remaining Sun Management Center 3.0 directories. The Sun Management Center 3.0 directories contain the information that will be migrated to Sun Management Center 3.6.

5. Upgrade the Solaris operating environment if necessary.

If you are installing the Sun Management Center 3.6 server, the machine must be running at least the Solaris version 8 or Solaris version 9 developer environment. For additional information, see [“Prerequisite Packages” on page 76](#)



Caution – If you need to upgrade to Solaris version 8 or Solaris version 9, make sure you perform a Solaris upgrade. A fresh Solaris installation reformats the hard drive, which deletes your Sun Management Center 3.0 configuration data. If you perform a fresh Solaris installation, you will not be able to migrate your Sun Management Center 3.0 configuration data to Sun Management Center 3.6.

Uninstalling Sun Management Center 3.6

The graphical `es-guiuninst` wizard can be used either to uninstall all of a Sun Management Center 3.6 installation, or to uninstall only specific add-on products. `es-guiuninst` also provides the option to back up the Sun Management Center 3.6 configuration data from the previous 3.6 version. If you chose to back up the configuration data, the Sun Management Center 3.6 installation process detects the backup and asks whether you want to apply the data to the new installation.

You can uninstall specific Sun Management Center 3.6 add-on products by using either the graphical `es-guiuninst` wizard as described below, or by using the `es-uninst` command-line script as described in [“Uninstalling Sun Management Center” on page 213](#).



Caution – (On Solaris 10) When you uninstall Sun Management Center 3.6 from the global zone, the local zone agent data will not be preserved.

▼ To Uninstall Sun Management Center 3.6 Using `es-guiuninst`

- Steps**
1. **Open a terminal window, then type the command `xhost +` in the terminal window.**
Also, make sure that the `DISPLAY` environment variable is set to your machine's display.
 2. **Log in as root on the machine where the Sun Management Center 3.6 software is installed.**
 3. **Remove T3 device configuration information if T3 devices are present.**
If you have not installed and set up the add-on Monitoring and Management of A5x00 and T3 Devices, skip this step. Go to [Step 4](#).

If you monitor and manage T3 storage devices using the Monitoring and Management of A5x00 and T3 Devices add-on, remove T3 device configuration information before you uninstall Sun Management Center. For instructions, see “Removing T3 Device Configuration If Present” on page 83 in Chapter 4.

4. Type the following command:

```
# /opt/SUNWsymon/sbin/es-guiuninst
```

The Welcome screen appears.

5. Click Next.

The Product Selection for Uninstall screen appears.

6. Select the products to uninstall.

7. Determine whether to save configuration data.



Caution – If you do not save the configuration data, your current Sun Management Center packages are uninstalled and the contents of `/var/opt/SUNWsymon` are removed. In addition, your security keys are overwritten and you must set up all agents again for the agents to work properly. Select Save Data if you want to retain your administrative domain configuration and custom alarm settings in `/var/opt/SUNWsymon` for subsequent installations or upgrades.

The Product Removal Confirmation screen appears.

8. Confirm your selections for uninstall.

The selections that you made are listed.

9. Click Close to exit the uninstall wizard.

10. Ensure that all components have been uninstalled.

Type the following command to list all Sun Management Center packages:

```
# pkginfo -c symon
```

If any packages are listed, uninstall each package using the `pkgrm` command. For example:

```
# pkginfo -c symon
SUNWesse
# pkgrm SUNWesse
```

Uninstalling Sun Management Center From the Microsoft Windows Platform

This section provides the procedure for uninstalling previous versions of the Sun Management Center Console from Microsoft Windows.

▼ To Uninstall Sun Management Center From Microsoft Windows

Before uninstalling Sun Management Center, make sure you do not have any Sun Management Center directories open in Windows Explorer. Also make sure no other applications are accessing Sun Management Center directories. If any Sun Management Center directories are accessed when you uninstall Sun Management Center, the uninstall process will not remove the Sun Management Center directories.

- Steps**
- 1. Log in as administrator, or as a user with administrator privileges.**
 - 2. Choose Start → Settings → Control Panel.**
The Control Panel window appears.
 - 3. Double-click Add/Remove Programs.**
The Add/Remove Programs window appears.
 - 4. Select Sun Management Center.**
 - 5. Click Change/Remove.**
A command window opens and displays the uninstall progress. When the uninstall completes, the command window closes.
 - 6. Click Close in the Add/Remove Programs window.**

Using the Command Line for Uninstall, Install, and Setup

This appendix provides the procedures for using the command-line interface to uninstall, install, and set up Sun Management Center.

The following topics are provided:

- “Uninstalling Sun Management Center” on page 213
- “Installing Sun Management Center Using `es-inst`” on page 217
- “Setting Up Sun Management Center Using `es-setup`” on page 229

Uninstalling Sun Management Center

This section provides a summary of the `es-uninst` options, and the procedure for using the `es-uninst` command-line script to uninstall Sun Management Center from Solaris systems.

`es-uninst` Options

The syntax for the `es-uninst` command is:

```
es-uninst [ -f | -F | -X | -h | -v ]
```

The following table describes the `es-uninst` command parameters.

TABLE B-1 `es-uninst` Options

Option	Description
-F	Uninstall the entire Sun Management Center installation without prompting for confirmation and without stopping any running Sun Management Center processes. This option should be used only in a situation when the executables that are called while stopping Sun Management Center processes are not present where expected. For example, if the operating environment has been upgraded after Sun Management Center was installed from the Solaris 7 release to the Solaris 8 release, then some dynamically generated path names will be incorrect. In this case, this option avoids errors being reported during the uninstall process.
-f	Uninstall the entire Sun Management Center installation without prompting for confirmation.
-h	List the <code>es-uninst</code> options.
-v	Perform the uninstall using verbose mode.
-X	Complete Sun Management Center uninstall without interaction. All processes are stopped, then the entire Sun Management Center installation, including the database and all add-ons, is removed. You are not given the opportunity to save your configuration data.

Uninstalling Sun Management Center Versions 2.x and 3.x

The Sun Management Center 2.x and 3.x `es-uninst` command is used to uninstall all of a Sun Management Center 2.x or 3.x installation. The Sun Management Center 2.x and 3.x `es-uninst` command also provides the option to back up the Sun Management Center configuration data. If you chose to back up the configuration data, the Sun Management Center 3.6 installation process detects the backup, and asks whether you want to apply the data to the new installation.

You can uninstall Sun Management Center 2.x and 3.x by using the `es-uninst` command-line script, as described below.

Note – The Sun Management Center 3.6 installation process automatically runs the `es-uninst` uninstall script of an existing Sun Management Center 2.x or 3.x installation. The Sun Management Center 2.x and 3.x `es-uninst` uninstall script gives you the opportunity to back up the configuration data from the previous version so that it can be applied to a new Sun Management Center 3.6 installation.



Caution – (On Solaris 10) (On Solaris 10) When you uninstall Sun Management Center 3.6 from the global zone, the local zone agent data will not be preserved.

▼ To Uninstall Sun Management Center 2.x and 3.x Using `es-uninst`

The following steps assume that you installed Sun Management Center in the default directory `/opt`. If you installed Sun Management Center in a different directory, replace `/opt` with the name of the directory you specified.

Steps 1. **Log in as root on the machine where the Sun Management Center 2.x or 3.x server is installed.**

2. **Remove T3 device configuration information if T3 devices are present.**

If you have not installed and set up the add-on Monitoring and Management of A5x00 and T3 Devices, skip this step. Go to [Step 3](#).

If you monitor and manage T3 storage devices using the Monitoring and Management of A5x00 and T3 Devices add-on, remove T3 device configuration information before you uninstall Sun Management Center. The `es-uninst` command does not remove T3 device configuration information.

To remove T3 device configuration information:

a. Stop the Sun Management Center agent.

Type the command `/opt/SUNWsymon/sbin/es-stop -a`.

b. Run the pre-uninstall script to remove T3 device configuration information.

Type the command
`/opt/SUNWsymon/addons/storage/sbin/pre-uninst.sh`.

You are asked whether you want to stop the T3 from sending syslog messages. Type **y**. You are then prompted for the root password for the T3 device. Type the password.

You are notified that the T3 device has been removed from the T3 module.

- If you do not run the `pre-uninst.sh` script before you install Sun Management Center 3.6, you will have to manually remove T3 configuration information before you can set up the new Sun Management Center 3.6 installation.
- If you run the `pre-uninst.sh` script but then decide to keep your Sun Management Center 2.x or 3.x installation, type the command `/opt/SUNWsymon/es-setup -F` to set up your T3 devices again.

You can now uninstall Sun Management Center.

3. To uninstall Sun Management Center 2.x or 3.x, type the command:

```
# /opt/SUNWsymon/sbin/es-uninst
```

- If you are uninstalling Sun Management Center 2.x or 3.x, you are asked whether you want to save your user and configuration data. Go to [Step 7](#).
- If you are uninstalling Sun Management Center 3.6, a list of products that are installed is displayed.

You are then asked whether you want to uninstall the Sun Management Center production environment or developer environment, depending on whether the production or developer environment is installed.

4. Select the Sun Management Center 3.6 products that you want to uninstall.

- Type **y** to uninstall the production or developer environment and all add-ons. You are notified that all Sun Management Center products will be uninstalled, and you are asked whether you want to change your selection. Go to [Step 6](#).
- Type **n** if you only want to uninstall one or more add-ons.

5. Select the Sun Management Center 3.6 add-on products that you want to uninstall.

The uninstall process steps through each add-on installed on your system. You are asked whether you want to uninstall the add-on.

Type **y** to uninstall the add-on, or type **n** to keep the installed add-on.

When you have completed your selections, a list of the products you selected for uninstall is displayed. You are asked whether you want to change your selections.

6. Change selections if needed.

- Type **y** to make different selections. The list of installed products is displayed again, and the uninstall selection process is repeated.
- Type **n** to continue the uninstall process. You are asked whether you want to preserve the your user and configuration data.

7. Save the Sun Management Center user and configuration data if needed.



Caution – If you reply **n**, your current Sun Management Center user and configuration data, including the database, will be removed. In addition, your security keys will be overwritten, and you will also need to set up all agents for the agents to work properly.

- Reply **y** if you want to retain your administrative domain configuration and custom alarm settings in `/var/opt/SUNWsymon` for subsequent installations or upgrades.

- Type **n** to discard the existing database.

You are asked whether you want to proceed with the uninstall.

8. Complete the uninstall process.

- Type **y** to uninstall the product or products that you have selected.
Your selection or selections are uninstalled. When the process completes, the `es-uninst` script exits to the command prompt.
- Type **n** if you do not want to uninstall the selected products.
The `es-uninst` script exits to the command prompt.

Installing Sun Management Center Using `es-inst`

This section describes how to install the product on Solaris and Linux systems using the `es-inst` script. During installation, you may install the console, server, and agent layers either separately or in combination. You may also choose specific add-on products for the features that you want to install. When the install process is completed, the setup script `es-setup` is run, enabling you to set up the base and add-on components.

Note – On Linux, agent and console layers can be installed. Remote installation is not possible using `es-inst`.

Note – If you plan to install the Sun Management Center 3.6 development environment, you should install the developer environment on a separate, dedicated machine. The Sun Management Center server, agent, and console layers are automatically installed on a developer environment machine. A machine used for Sun Management Center development must meet the minimum hardware and software requirements for the Sun Management Center server layer. The developer environment machine must also meet the requirements for the agent layer, console layer, and any add-ons you install. For more information, see [Chapter 1](#).

`es-inst` Options

The syntax for the `es-inst` command is:

```
es-inst [-S dir] [-T dir] [-R dir] [-C file] [-A file] [avh]
```

The following table describes the `es-inst` parameters.

TABLE B-2 `es-inst` Options

Option	Modifying Options	Description
-A	<i>filename</i>	Perform an automated installation using the specified configuration file <i>filename</i> . This option is ignored if <code>-C</code> is also used.
-C	<i>filename</i>	Specify a file in which to store the configuration details entered during installation and setup. The file can be used for subsequent automated installation.
-R	<i>/path/remote-machine</i>	Install Sun Management Center on a <i>remote</i> machine that is network file system read/write accessible from the root login account on the <i>local</i> machine. See "Installing on a Remote Machine" on page 224.
-S	<i>directory</i>	Specify the source directory.
-T	<i>directory</i>	Specify the target directory.
-a		Perform an agent-only product installation. See "To Install or Update Agents From an Agent-Update Image Using <code>agent-update.bin</code>" on page 122.
-h		List the <code>es-inst</code> options.
-v		Perform an installation using verbose full log mode.

Installing on a Local Machine

This installation procedure assumes you are installing Sun Management Center from a cd-image directory on your network. See ["Creating Installation CD Images" on page 85](#) for further information. This procedure also assumes that you have not specified any of the `es-inst` parameters.

▼ To Install Using the `es-inst` Script

- Steps**
1. Log in as root on the machine where you want to install Sun Management Center.

2. In the `/etc/nsswitch.conf` file, ensure that the group entry has files as the first token.

```
group: files nis
```

3. Review the README files.

- `/net/machine-name/cd-imagedir/disk1/sbin/README.INSTALL`
- `/net/machine-name/cd-imagedir/disk1/sbin/INSTALL_README.HWDS`

where `/net/machine-name/cd-imagedir` is the path to the network machine where you created the Sun Management Center installation cd-image.

4. Go to the Sun Management Center installation disk 1 `sbin` directory.

- If you are installing from disk, and then go to the `/<DiskMountDir>/sbin` directory.
During the installation process, you might be prompted to change CD disks depending on your selections.
- If you are installing from a CD image, go to the `/cd-image-dir/disk1/sbin` directory, where `cd-image-dir` is the directory either where you copied the installation CDs, or where you downloaded and untarred the installation image from the Web.

5. Run the `es-inst` installation script:

```
#!/es-inst
```

- If a prior version of Sun Management Center is not installed on the system, you are prompted for the target directory. Go to [Step 8](#).
- If Sun Management Center 2.x or 3.0 is installed on the system, you are asked whether you want to uninstall the previous Sun Management Center version.

6. Uninstall the previous version.

You are asked whether you want to uninstall the previous version. You cannot install Sun Management Center 3.6 until the previous version is uninstalled.

- Type `n` or `q` if you do not want to uninstall the previous version. You are returned to the system prompt.
- Type `y` to uninstall the previous version.
You are asked whether you want to migrate the data from the previous installation of Sun Management Center.

7. Migrate previous version data.

The administrative domain configuration data, custom alarm settings, and scripts from your previous installation of Sun Management Center 2.x or 3.0 can be saved and applied to the new installation of Sun Management Center 3.6. The data is located in `/var/opt/SUNWsymon`.

- Type `y` to save and migrate the data from the previous version of Sun Management Center.

The installation process stops any Sun Management Center processes that are running. The data is saved to `/var/opt/SUNWsymon.bak`.

- Type **n** to discard all data from the previous version of Sun Management Center.

The installation script warns you to move any custom scripts that you want to save.



Caution – If you have custom scripts stored in any directory under `/var/opt/SUNWsymon` that you want to use in Sun Management Center 3.6, move them to an alternate location before going to [Step 6](#).

The installation process then runs the previous Sun Management Center version's `es-uninst` script to uninstall the previous version.

Note – The uninstall process can take anywhere from a few minutes to half an hour, depending on the products and add-ons installed in the previous version.

During the uninstall process, you might see messages that state package removal failed. You can ignore these messages. Any package that is not removed at first is removed later by the uninstall process.

When the uninstall process completes, you are prompted for the directory in which to install Sun Management Center.

8. Type the name of the directory in which to install Sun Management Center

The default location is `/opt`.

Sun Management Center software can be installed in any location on your system where the minimum required disk space is available. Press Return to accept the default location `/opt` or, if you want to install to a directory other than `/opt`, type the directory name.

Tip – The command `df -ak` lists the used space and free space for each file system on the machine.

You are asked whether you want to install either the production environment or the developer environment.

9. Select either the Production Environment or Developer Environment.

Note – You should install and run the Sun Management Center developer and production environments on separate, dedicated servers.

Type **1** to install the production environment, or type **2** to install the developer environment.

- If you selected Developer Environment, all Sun Management Center base components are installed:
 - Server layer
 - Agent layer
 - Console

The Server Layer Binary Code License is displayed. Go to [Step 11](#).

- If you selected Production Environment, you are prompted to select the Sun Management Center component layers that you want to install.

10. Select the Sun Management Center component layers that you want to install.

You are asked to reply **y** or **n** to each layer. For example:

```
Select the Sun Management Center Architectural Component Layers:
3 Layer(s) are available for your selection:
Do you want to install Server Layer Components ? [y|n|q]  y
    The Server Layer has been selected for install.
    The Sun Management Center Agent will be installed automatically.
Do you want to install Console Layer Components ? [y|n|q]  y
```

Note – If you select Server, Agent is automatically selected.

- If you selected Server, or selected Server, Agent, and Console, the Server Layer Binary Code License is displayed. Go to [Step 11](#).
- If you selected Console, or Agent and Console, the Select Language Support screen appears. Go to [Step 12](#).
- If you selected Agent only, the Select Add-on Products screen appears. Go to [Step 13](#).

11. Review the Server Layer Binary Code License.

Read the Server Layer Binary Code License carefully. To continue the installation, you must agree to the terms of the license.

Type **y** to agree to the license and continue, or type **n** to exit the installation.

- If a valid JDK version is not installed, you are informed which version is needed. The installation process then exits to the system prompt.

- If you accept the license, the installation process checks for a valid JDK version. If a valid JDK version is installed, you are prompted to select additional language support.

Note – The Sun Management Center Web server and online help are installed with the server layer.

12. If you want to install the product in additional languages, select the appropriate languages.

- If you want to install additional language support, type **y**.
You are asked to reply **y** or **n** to each language.
- If you do not want to install additional language support, type **n**.

When you have completed language selection, the install process checks for add-on products.

13. Select the Sun Management Center add-on products.

The install process lists each add-on product, and asks if you want to install the product. Type **y** to select the product for installation, or type **n** if you do not want to install the product.

- Some add-ons are platform-specific. For information about each add-on, refer to the platform supplements provided with the Sun Management Center release kit, and to the Sun Management Center Web site at <http://www.sun.com/sunmanagementcenter/>.

Note – If you want to use the Sun StorEdge A5x00 add-on product, see [“Sun StorEdge A5x00 Packages” on page 81](#) before continuing.

- Some add-ons have optional components. If optional add-on components are available, the components are listed sequentially. Type **y** to select the optional component for installation, or type **n** if you do not want to install the optional component.

If you did not select any add-on products, you are asked whether you want to proceed. Type **y** to continue. The install process checks disk space. Go to [Step 16](#).

If you selected any add-ons, your selections are listed.

14. Review your selections.

Type **y** to continue, or type **n** to repeat the selection process.

- If you selected only the agent, or agent and console during component selection, and selected any add-on products, the installation process checks disk space. Go to [Step 16](#).

- If you selected the server during component selection, and selected any of the following add-on products, the Add-on Products Binary Code License is displayed. Go to [Step 15](#).
 - Advanced System Monitoring
 - Performance Reporting Manager
 - Service Availability Manager
 - Solaris Container Manager
 - System Reliability Manager
- If you did not select any of the above add-on products but did select other add-on products, the installation process checks disk space. Go to [Step 16](#).

15. Review the Add-on Products Binary License.

Read the Add-on Products Binary Code License carefully. To continue the installation, you must agree to the terms of the license.

Type **y** to agree to the license or **n** to exit the installation.

If you typed **y** to agree to the license and did not select additional add-on components, the installation process checks disk space.

16. Check disk space.

The installation process checks whether there is enough disk space to install the products that you selected.

- If there is enough disk space, the products that you selected are installed.

Note – The installation process can take from a few minutes to half an hour or more, depending on the products selected.

When the installation process completes, a list of installed products is displayed. You are asked whether you want to set up the Sun Management Center components. Go to [Step 18](#).

- If there is not enough disk space, you are asked to provide an alternate file system. The amount of space available and the amount of space that is needed are displayed.

17. Provide the name of an alternate file system with enough disk space.

At the prompt requesting a different file system, type the name of a file system and directory that has enough free space.

Tip – In a terminal window on the machine where you are installing Sun Management Center, type **df -ak** to list the amount of used and free space for each file system on the machine.

The installation process checks disk space again. If there is enough disk space, the products that you selected are installed.

Note – The installation process can take from a few minutes to half an hour or more, depending on the products selected.

When the installation process completes, a list of installed products is displayed. You are asked whether you want to set up the Sun Management Center components.

18. Decide whether to set up the installed products.

Type **y** to set up Sun Management Center and any add-on products that you selected, or type **n** to exit and run setup later.



Caution – If you have used `es-inst` to install *only* add-on products, type **n** to exit the installation and setup process. You must set up the add-on products as described by [“To Set Up an Add-on Product Using `es-setup`” on page 162](#). Otherwise, you will overwrite your security keys, and will then have to set up all of the agents on all of your machines for the agents to work properly.

- If you typed **y** to run setup now, follow the instructions in [“Setting Up Sun Management Center 3.6 Using `es-setup`” on page 230](#).
- If you typed **n** to run setup later, you must set up the agent on the machine before you can run the agent.
 - To set up the agent using `es-guisetup`, follow the instructions in [“To Set Up Sun Management Center” on page 33](#).
 - To set up the agent using `es-setup`, follow the instructions in [“Setting Up Sun Management Center 3.6 Using `es-setup`” on page 230](#).

Installing on a Remote Machine

This section provides the procedure for installing Sun Management Center 3.6 on a Network File System accessible (NFS-mounted) remote machine using the `es-inst` command. The procedure assumes that you are installing Sun Management Center from a cd-image directory on your network. See [“Creating Installation CD Images” on page 85](#) for further information.

To install Sun Management Center on a remote machine, you have to prepare the remote machine before you install the software. Also, if the local machine is running Solaris 2.6, Solaris 7, or Solaris 8 software, you must install a patch as described in [“To Install Patches for `pkgadd`” on page 225](#).

The following machine names are used as examples in the procedures in this section:

- *admin-host* is the local machine used to perform the installation on the remote machine.
- *remote* is the remote machine on which you want to install Sun Management Center.

Note – Remote installation is not supported if the remote machine is a Solaris 10 machine.

▼ To Install Patches for pkgadd

If the local machine is running Solaris 2.6, Solaris 7, or Solaris 8 software, a patch for pkgadd specific to the operating system version must be installed on the local machine. You must install this patch before you can use the local machine to install Sun Management Center 3.6 on the remote machine.

If the local machine is running the Solaris 9 release, you do not need to install any patches. Go to [“To Prepare the Remote Machine” on page 226](#).

Steps 1. Log in as root on the *local* machine.

2. Ensure that the OS patch level is current.

To determine whether the patch is already installed, use the command `showrev -p | grep patchnum`, where *patchnum* is the required OS patch as follows:

- Solaris 2.6 release: 106292
- Solaris 7 release: 107443
- Solaris 8 release: 110934

For example, if the local machine is running Solaris 8 release, you would type:

```
admin-host# showrev -p | grep 110934
admin-host#
```

In the above example, the patch is not installed. The patch must be downloaded and installed as directed by [Step 3](#).

If the patch is installed, a listing similar to the following is displayed.

```
admin-host# showrev -p | grep 110934
admin-host# Patch: 110934-13 Obsoletes: Requires: Incompatibles:
Packages: pkgtrans, pkgadd, pkgchk
```

If the patch that is required by the local machine Solaris version is installed, go to [“To Prepare the Remote Machine” on page 226](#).

3. Install the OS patch if needed.

- a. Download the required patch from <http://www.sunsolve.sun.com>.

- b. Untar and then unzip the downloaded patch archive file.
- c. Install the patch using the `patchadd` command.

▼ To Prepare the Remote Machine

- Steps**
1. Log in as root on the *remote* machine.
 2. Create the Sun Management Center database access group and user account.
 - a. Use the `groupadd` command to create the access group `smcorag`.

```
remote# /usr/sbin/groupadd smcorag
```

- b. Create the directory `/var/opt/SUNWsymon`.
This directory is where the database user account will be located.

```
remote# mkdir -p /var/opt/SUNWsymon
```

- c. Use the `useradd` command to create the database user account `smcorau`, and then add the user account to the group `smcorag`.

```
remote# /usr/sbin/useradd \  
...-d /var/opt/SUNWsymon/smcorau \  
-m -g smcorag -s /bin/sh smcorau
```

3. Stop the Network File System daemon `mountd`.
4. Edit the `/etc/dfs/dfstab` file on the remote host.
Add the following line:

```
share -F nfs -o rw=admin-host,root=admin-host /
```

where *admin-host* is the name of the machine from which you will install Sun Management Center onto the remote host.

For example, if the remote host name is *remote-server*, and the name of the machine you will use to install Sun Management Center on *remote-server* is *adminserver*, then the entry in the *remote-server* `/etc/dfs/dfstab` file would be:

```
share -F nfs -o rw=adminserver,root=adminserver
```

This entry in the remote machine's `dfstab` file gives remote read and write permission only to the root user account logged on to the machine *adminserver*.

5. Save and close `/etc/dfs/dfstab`.
6. Start the Network File System daemon `mountd`.

```
remote# /etc/init.d/nfs.server start
```

7. Determine the Solaris version running on the remote machine.

```
remote# /usr/bin/uname -r
```

When you install Sun Management Center on the remote host, the `es-inst` script will prompt you for the Solaris version running on the remote host.

8. Determine the remote host machine type.

When you install Sun Management Center on the remote host, the `es-inst` script will prompt you for the remote machine type.

The information required by `es-inst` for the remote host machine is generated by the command:

```
remote# /usr/platform/platform/sbin/prtdiag | /usr/bin/head -1 \  
      | /usr/bin/cut -f2 -d:
```

where *platform* is the output of the command `uname -i`.

For example:

```
remote# /usr/bin/uname -i  
SUNW,Ultra  
remote# /usr/platform/SUNW,Ultra/sbin/prtdiag  
      | /usr/bin/head -1 | /usr/bin/cut -f2 -d:  
Sun Microsystems sun4u Sun Ultra UPA/PCI (UltraSPARC-III 333 MHz)
```

Tip – Copy the remote host machine-type information to a temporary file on the local host. You can then paste the information when `es-inst` prompts you for the remote host machine type.

9. Log off the remote machine.

You can now install Sun Management Center on the remote host as described by the next procedure.

▼ To Install Sun Management Center on the Remote Machine

- Steps**
1. Log in as root on the *local* machine.
 2. Change to the Sun Management Center installation disk 1 `sbin` directory.
 - If you are installing from disk, then Change to the `/c<DiskMountDir>/sbin` directory.During the installation process, you might be prompted to change CD disks depending on your selections.

- If you are installing from a CD image, Change to the `/cd-image-dir/disk1/sbin` directory, where *cd-image-dir* is the directory either where you copied the installation CDs, or where you downloaded the installation image from the Web.

3. Run the `es-inst` installation script, and specify the remote host machine using the `-R path/remote` parameter.

```
#!/es-inst -R path/remote
```

where *path/remote* is the full path to the remote machine. For example, if the remote host path and name is `/net/remote-server`, you would type:

```
local-machine# ./es-inst -R /net/remote-server
```

You are prompted for the Solaris version running on the remote machine.

4. Type the Solaris version running on the remote machine.

See [“To Prepare the Remote Machine” on page 226, Step 7.](#)

You are prompted for the remote host machine type.

5. Provide the remote host machine type.

Type the machine type string that you generated in [“To Prepare the Remote Machine” on page 226, Step 8.](#) Alternately, if you copied the generated text to a file on the local host, you can paste the machine-type string in answer to the prompt.

Note – The steps that are required to complete installation of Sun Management Center on a remote host are the same steps that are required for the default Sun Management Center install.

6. Complete the installation.

- If Sun Management Center 2.x or 3.0 is installed on the system, you are asked whether you want to migrate the data from the previous Sun Management Center version. Go to [“To Install Using the `es-inst` Script” on page 218, Step 7.](#)
- If a prior version of Sun Management Center is not installed on the system, you are prompted for the target directory. Go to [“To Install Using the `es-inst` Script” on page 218, Step 8.](#)

Note – Remote installation on to a Solaris 10 system is supported only from another Solaris 10 system.

Setting Up Sun Management Center Using `es-setup`

This section describes how to install the product on the Solaris platform using the `es-setup` script. During installation, you may install the console, server, and agent layers either separately or in combination. You may also choose specific add-on products for the features that you want to install. When the install process is completed, the set up script `es-setup` is run, enabling you to set up the base and add-on components.

When to Run Setup

You should run the setup process in the following situations:

- When you have completed installing Sun Management Center 3.6 for the first time but have not run setup
- When you change your setup configuration, such as changing the server context
- When instructed to do so in your add-on software or hardware supplement
- When you need to reconfigure your entire Sun Management Center 3.6 installation
- When you need to set up a new add-on product
- When you need to re-create the Sun Management Center database

`es-setup` Options

The syntax for the `es-setup` command is:

```
es-setup [ -A file ] [ -C file ] [ -p directory ] [ -Fhrvw ] [ -z Zone
```

The following table describes the `es-setup` parameters.

TABLE B-3 `es-setup` Options

Option	Modifying Options	Description
<code>-A</code>	<i>filename</i>	Perform an automated setup using the specified response setup file <i>filename</i> . Note – This option is ignored if <code>-C</code> is also used.

TABLE B-3 *es-setup* Options (Continued)

Option	Modifying Options	Description
-C	<i>filename</i>	Specify a file in which to store the setup responses that you provide during the setup process. The setup responses file can be used for subsequent automated setup. This option supersedes the -A option.
-F		Set up the entire Sun Management Center installation again, including all installed base products, database, and add-ons. Use of this option is equivalent to resetting the entire installation to a post-install and pre-setup state, and then running setup.
-h		List the <i>es-setup</i> options.
-k		Perform setup without generating security keys.
-p	<i>directory</i>	Set up a single add-on where <i>directory</i> is the directory name for the add-on. For example, the storage add-on is in <code>/opt/SUNWsymon/addons/storage</code> . To set up the storage add-on using <i>es-setup</i> , you would type <code>es-setup -p storage</code> . Use of this option is equivalent to resetting the specified add-on to a post-install and pre-setup state, and then running setup for the single add-on.
-r		Recreate the database. No other setup is performed.
-v		Perform setup using verbose mode.
-w		Skip Database re-setup. This option is valid with the -F option.
-z		Setup agent to be run in zone

Setting Up Sun Management Center 3.6 Using *es-setup*

This section provides the procedure for setting up Sun Management Center. This procedure assumes that you have not specified any of the *es-setup* parameters.

▼ To Set Up Sun Management Center Using the `es-setup` Script

Steps 1. Log in as root on the machine where you installed Sun Management Center.

2. Change to the Sun Management Center `sbin` directory. For example:

```
# cd /opt/SUNWsymon/sbin
```

If you installed Sun Management Center in a different directory than `/opt`, change to `/installdir/SUNWsymon/sbin`, where *installdir* is the directory you specified.

3. Run the `es-setup` script.

```
# ./es-setup
```

- If you installed only the Sun Management Center console, the setup process sets up the console and then runs setup for any add-ons you selected. Go to [Step 16](#).
- If you installed only the agent, or agent and console, you are prompted to provide a password for security key generation. Go to [Step 5](#).
- If you installed the Sun Management Center server, the setup process checks for DB listener port conflict.
 - If the DB listener port is not in use and the system has sufficient memory, you are prompted to provide a password for security key generation. Go to [Step 5](#).
 - If the DB listener port is not in use, and the system does not have sufficient memory, the amount of memory that is available and the amount of memory that is needed is displayed. The setup process exits to the system prompt. Take steps to make enough memory available, and then run setup again.
 - If the DB listener port is in use, you are prompted to assign an unused port.

4. **Resolve DB listener port conflict**

Press Return to accept the alternate default port 2522, or type the number of an unused port. “[To Determine Whether a Port Is Used](#)” on page 184 describes how to determine whether a port is in use. “[Reconfiguring Sun Management Center Ports](#)” on page 185 describes how to use the `es-config` command to reassign Sun Management Center ports.

The setup process checks the available memory.

- If the system has sufficient memory, you are prompted to provide a password for security key generation. Go to [Step 5](#).
- If the system does not have sufficient memory, the amount of memory that is available and the amount of memory that is needed is displayed. The setup process exits to the system prompt. Take steps to make enough memory available, and then run setup again.

5. Generate the Sun Management Center security key.

An encrypted security key is needed for communications between all Sun Management Center processes. The key is generated based on the password you provide, which must be between one and eight characters long, and contain no spaces. Entries that are greater than eight characters are truncated to eight characters.

Note – Keep a record of the password that you use to generate the security key for this machine in a secure location in case you need to regenerate the key for the machine at a later time. You can also change the security key later, if needed, as described in “Regenerating Security Keys” on page 178.

a. Type the password for the seed to generate the security keys.

b. Type the password again.

You are prompted for the SNMPv1 community string.

6. Specify the SNMPv1 community security string.

The community string is used for SNMP security, and is set to `public` by default.

Set the community string to a value other than `public` or `private` to provide better SNMP security.



Caution – The same SNMP community string must be used on all of the machines on which you install Sun Management Center 3.6. If you use different community strings on each machine, SNMP communications between the machines and Sun Management Center components will not work. Keep a record of the community string that you used in a secure location in case you need to specify the community string again at a later time.

- If you want to accept the community string default value of `public`, press Return when prompted to submit the SNMPv1 community string.
- If you want to use a custom community string, type the community string text. The community string can be up to 255 characters in length, but must not contain any spaces or blanks.

You are prompted to retype the SNMPv1 community string to confirm the string. Type the same string. For example:

```
This part of setup configures SNMPv1 read-only community string.  
Please make sure you use the same string on all the machines you install.  
You may like to keep record of this string for future use.
```

```
Hit RETURN key to force default value.
```

```
Please enter SNMPv1 community string: my-snmp-string
```

```
Please re-enter the SNMPv1 community string to confirm: my-snmp-string
```


The setup process checks which base components have been installed.

- If you installed only the agent, or agent and console, you are prompted for the .Sun Management Center server host name. Go to [Step 9](#).
- If you installed the server, the setup process checks for a valid UNIX administrator account name for the Sun Management Center `esadm` and `esdomadm` groups. See [“Users, Groups, and Roles Overview”](#) on page 65 for information about groups.
 - If a valid UNIX administrator account name exists, the setup process checks for server port conflicts. Go to [Step 8](#).
 - If a valid UNIX administrator account name does not exist, you are prompted for the UNIX administrator account name.

7. Type a valid Solaris/Linux user name as the UNIX administrator account name.

A valid Solaris/Linux user name is required for Sun Management Center administration. Type a valid Solaris/Linux user name.

The setup process checks for server port conflicts.

8. Resolve server port conflicts.

The setup process checks the ports needed by the Sun Management Center server to determine whether the ports are in use. If any ports are in use, you must assign an unused port. [“To Determine Whether a Port Is Used”](#) on page 184 describes how to determine whether a port is in use. [“Reconfiguring Sun Management Center Ports”](#) on page 185 describes how to use the `es-config` command to reassign Sun Management Center ports.

The ports are checked in the following order: topology service, configuration service, event service, cst service, trap service, metadata service, and look-up service.

- If no ports are in use and you have installed the Sun Management Center server, you are prompted for the information needed to generate the Web server security key. Go to [Step 10](#).
- If no ports are in use and you have not installed the Sun Management Center server, you are prompted for the Sun Management Center server host name. Go to [Step 7](#).
- If any ports are in use, you are prompted to either reconfigure the port, or to stop the process that is using the port.
 - To reconfigure a port, type the number of an unused port.
 - To use the default port, press Return.



Caution – If you chose to use the default port, you must manually review, identify, and then rename the `/etc/rcN` and `/etc/rcN.d` files that use the port, and then manually stop the processes that are using the port before you can start Sun Management Center.

Once all port conflicts are resolved, the setup process checks whether you installed the server.

- If you installed the Sun Management Center server, you are prompted for the information needed to generate the Web server security key. Go to [Step 10](#).
- If you have not installed the Sun Management Center server, you are prompted for the Sun Management Center server host name.

9. Specify the Sun Management Center server host name.

Type the name of the machine on which the Sun Management Center server was installed.

The setup process checks whether the SNMP port is in use. Go to [Step 12](#).

10. Specify the Web server security key.

An encrypted security key is needed for the Sun Management Center Web server. The key is generated based on the name of your organization and the name of your location. The names that you provide must not contain any spaces or blanks.

For example, you could type `administration` for the organization, and `headquarters` for the location.

Note – Keep a record of the entries that you use to generate the security key in a secure location in case you need to regenerate the key for a particular machine at a later time.

Type the name of your organization at the prompt. For example:

```
An encrypted security key is needed for the Sun Management Center
Web server. The key is generated based on the organization and location
you provide.
Please enter the name of your organization : administration
```

You are prompted for your geographical location. Type the name of your location at the prompt. For example:

```
Please enter the geographical location of this host : headquarters
```

The setup process checks whether the web server ports are in use.

- If the web server port and the web server secure port are not in use, the setup process checks whether SNMP port 161 is in use. Go to [Step 12](#).
- If the web server default port or secure port is in use, you are prompted to assign an unused port.

11. Resolve web server port conflicts.

Press Return to use the displayed default port, or type the number of a port that is not in use.



Caution – If you chose to use the default web server port or secure port, you must manually review, identify, and then rename the `/etc/rcN` and `/etc/rcN.d` files that use the port, and then manually stop the processes that are using the port before you can start Sun Management Center.

The setup process checks whether the SNMP port is in use.

- If SNMP port 161 is not in use, the setup process checks whether configuration data from a previous version of Sun Management Center has been saved. If you saved the configuration data from a previous Sun Management Center installation, you are asked whether you want to restore the data. Go to [Step 14](#).

If you did not save configuration data from a previous installation, or if this is the first time Sun Management Center has been installed on this machine, then the setup process lists the setup status for the core products you selected. Go to [Step 15](#).

- If SNMP port 161 is in use, you are prompted to assign an SNMP port number.

12. Resolve the SNMP port conflict.

You are notified that port 161 is in use by another process. In most cases, port 161 is the port that is assigned to and used by the SNMP daemon. However, other processes or daemons could be using port 161. Several third-party replacements and enhancements for the SNMP daemon exist, and could be installed on your system. The Sun Management Center agent is such a daemon.

You can choose to use port 161, or you can assign a different port number.



Caution – If you chose to restore the configuration data from a previous Sun Management Center installation, make sure you use the same port number as you had in the previous Sun Management Center installation for both agent and server upgrades.

a. **To assign a different port number, type an unused port number.**

For example:

```
Enter the port you want to use [ 1100 to 65535 ]: 1161
Updating /var/opt/SUNWsymon/cfg/domain-config.x with new port number.
```

Note – Keep a record of this alternate port number. You will need this number if you later install agents using the JumpStart software, or update the Sun Management Center agents using the agent update-image tools. For more information, see [“Installing Agents Using JumpStart” on page 126](#) and [“Creating Agent Installation and Update Images” on page 101](#).

If you did not save configuration data from a previous installation, or if this is the first time Sun Management Center has been installed on this machine, the setup process lists the setup status for the core products you selected. Go to [Step 15](#).

b. **To use port 161, press Return.**

You are informed that port 161 will be used by Sun Management Center, and that the SNMP daemon might be set to restart automatically when the system is rebooted.

You are asked whether you want to stop and disable the SNMPDX daemon.

13. Stop and disable the SNMP daemon.

- Type **y** to stop and disable the SNMP daemon.



Caution – Stopping and disabling the SNMP daemon is not a guarantee that you have stopped the actual process that is using port 161. If Sun Management Center fails to start after you have completed Sun Management Center setup, another process or daemon could be using port 161. As noted in [Step 12](#), you must manually review, identify, and then rename the `/etc/rcN` and `/etc/rcN.d` files that use port 161 to resolve the port conflict.

- Type **n** if you do not want to stop and disable the SNMP daemon.



Caution – You must stop all processes that use port 161 before you can start Sun Management Center.

The setup process checks for configuration data from a previous version of Sun Management Center.

- If you did not save configuration data from a previous installation, or if this is the first time Sun Management Center has been installed on this machine, the setup process lists the setup status for the core products you selected. Go to [Step 15](#).
- If you saved the configuration data from a previous Sun Management Center installation, you are asked whether you want to restore the data.

14. Restore previous Sun Management Center configuration data

The saved configuration data includes the graphs, topology objects, alarms, and other information that is displayed in the Sun Management Center console.



Caution – If you do not restore the configuration data from the previous installation of Sun Management Center, you will have to manually re-create the information.

- To restore the configuration data, type **y** and press Return. The configuration data from the previous Sun Management Center is restored.
- To discard the configuration data, type **n** and press Return. The configuration data from the previous Sun Management Center is deleted.

The setup process lists the setup status for the core products you selected.

15. Finalize the base product setup process.

- If base product setup failed, you are informed that the setup of the base products was not successful. You are then directed to see the log file for more details. The name of the log file is provided. The setup process exits to the system prompt.
Review the log file to determine the cause of setup failure.
- If base product setup succeeded, and you selected one or all of the base products only (console, agent, and server), you are asked whether you want to start the Sun Management Center components. Go to [Step 17](#).
- If base product setup succeeded and you selected any add-on products, the setup process runs the setup script for each add-on product you selected.

16. Set up add-on products.

Some add-on products are included with the Sun Management Center 3.6 installation CDs. These add-ons are the ones listed in [Step 13](#), in the procedure “[To Install Using the es-inst Script](#)” on [page 218](#). To set up each add-on, refer to the Sun Management Center supplement for each add-on, which is included in your installation kit. Each supplement provides the setup procedure for the specific add-on. The setup procedure for add-ons is therefore not duplicated here.



Caution – If you selected the add-on Monitoring and Management of A5x00 and T3 Devices, apply the necessary patches to the server as described in [“Sun StorEdge A5x00 Packages” on page 81](#). Also, add the T3 IP address, Ethernet address and name to the server system files as described in [“T3 Storage Devices” on page 81](#).

When the add-on setup is completed, the setup process lists the setup status for the add-on products.

- If add-on product setup failed, you are informed that the setup of the add-on product was not successful. You are then directed to see the log file for more details. The name of the log file is provided. The setup process exits to the system prompt.
Review the log file to determine the cause of setup failure.
- If add-on setup succeeded, you are asked whether you want to start the Sun Management Center components.

17. Start Sun Management Center 3.6.



Caution – If your network uses Network Address Translation (NAT), type **n** to exit setup without starting Sun Management Center. Use the `es-config` command-line utility described in [“To Enable NAT Support” on page 197](#) to configure the machine for NAT before you start Sun Management Center.

- If you want to start Sun Management Center now, type **y**.
The setup script starts Sun Management Center using `es-start -A`. See [“Starting Components Using es-start” on page 167](#) for information about `es-start`.
Also, see [“Starting the Console” on page 168](#) for instructions on how to start the Sun Management Center console.
- If you want to start Sun Management Center later, type **n**. See [Chapter 8](#) when you are ready to start Sun Management Center.

Determining Hardware Resources

This appendix provides guidelines for selecting the appropriately sized hardware for the Sun Management Center basic management framework and base add-on products. The Sun Management Center basic management framework and each base add-on product have specific disk space requirements for the Sun Management Center core layers agent, server, and console.

This chapter discusses the following topics:

- “Agent Layer Resources” on page 239
- “Server Layer Resources” on page 245
- “Java Console Layer Resources” on page 252
- “Sun Management Center Server with the Performance Reporting Manager Add-on” on page 247
- “Sun Fire Proxy/Platform Agent Resources” on page 252

Note – The information provided in this section does not take into consideration any third-party modules, nor are such modules reflected in any of the sizing figures.

Agent Layer Resources

Sun Management Center 3.6 agents should be installed on every managed node in your network to enable advanced management and monitoring functions. Sun Management Center agents are supported on any SPARC platform workstations and servers running Solaris version 2.6, Solaris version 7, Solaris version 8, Solaris version 9, or Solaris version 10. Sun Management Center agents are also available for Solaris operating system (x86 Platform Edition) systems running Solaris 9 and Solaris 10 and on Linux.

x86 Agent Limitations

Note – The same limitations apply for the Linux agent.

The x86 agents do not support any hardware-specific add-ons. The x86 agents have modules under the Operating System, Local Applications, and Remote Systems categories of the Module Browser tab in the Host Details window. Features such as Physical View, Logical View, Hardware Diagnostic module, and the Config-Reader module are not yet available on the Solaris x86 platform.

In the Java Console window, all x86 platforms have the same x86 icon. For example, two different x86 platform machines, such as the Sun Cobalt LX50 and the Sun Fire V60x, would both have the same icon.

You can filter by platform type when you use the Discovery feature, the Manage Jobs feature, or the PRM add-on. You can filter for the x86 platform by selecting x86 as the platform option.

For the Performance Reporting Manager (PRM) add-on, no system reports and hardware configuration reports are available.

CPU Resources

Sun Management Center agents add a minimal computational load on the host system. The computational load is caused by normal management operations, including periodic data acquisition, alarm rule processing, alarm annunciation, alarm action execution, and the processing of client requests.

The amount of load introduced is proportional to the rate at which data is gathered, the amount of data gathered, the number of alarms detected, and the number of user requests. The percentage of CPU resources consumed therefore depends on the number and type of modules loaded on the system, the configuration of these modules, and the computational capacity of the host system.

Even on low-end machines with a comprehensive suite of modules loaded and high management activity, the agent should never consume more than a fraction of the CPU resources.

The following table gives estimates of the agent CPU and RAM usage by system type and includes information for the x86 agent.

TABLE C-1 Agent CPU and RAM Use Estimates by System Type

Server Type	Heavy or Light Configuration	CPU Usage			RAM Usage	
		Maximum	Minimum	Average	Average Size	Average Resident Size
Sun Blade 100	Light	0.10%	0.00%	0.21%	8.77 Mbytes	7.02 Mbytes
Sun Fire 280R	Light	0.10%	0.00%	0.10%	10.47 Mbytes	8.49 Mbytes
Sun Blade 2000	Light	0.20%	0.00%	0.05%	8.89 Mbytes	7.06 Mbytes
Sun Fire 880	Light	0.00%	0.00%	0.00%	8.97 Mbytes	7.31 Mbytes
Sun Blade 100	Heavy	1.20%	0.50%	0.79%	14.83 Mbytes	12.99 Mbytes
Sun Fire 280R	Heavy	2.60%	0.10%	0.81%	16.22 Mbytes	13.92 Mbytes
Sun Blade 2000	Heavy	0.30%	0.20%	0.20%	14.45 Mbytes	12.76 Mbytes
Sun Fire 880	Heavy	4.40%	0.10%	0.88%	16.15 Mbytes	14.41 Mbytes

Light configurations are based on an agent with the following modules loaded:

- Kernel-Reader Simple
- Agent Statistics
- MIB-II Simple

The heavy configuration is based on an agent with the following modules loaded:

- Config Reader
- Health Monitor
- Full Kernel Reader
- MIB-II Instrumentation
- Directory Size Monitoring
- File Scanning
- Hardware Diagnostics Suite
- Script Launcher
- HP JetDirect
- Agent Statistics
- MIB-II Proxy Monitoring
- Various other modules, including custom modules

The heavy configuration is likely to be greater than needed. Larger machines typically have larger hardware configurations with more processors and disks. These configurations result in greater memory consumption by agents running on larger machines.

Virtual Memory Requirements

The virtual memory used by an agent depends on multiple factors. The primary considerations are the number of management modules loaded and the amount of information being monitored by these modules. Loading many modules on an agent increases its memory requirement. Similarly, agents managing hosts with large disk arrays or other highly scalable assets will probably require more virtual memory because the volume of management information passing through the agents will increase.

In general, a base agent with the default set of management modules loaded is under 10 Mbytes in size. The base agent requires only 50% to 60% of the 10 Mbytes to be resident in physical memory.

Hardware-Specific Module Availability

The majority of Sun Management Center management modules are portable across all SPARC platform systems running Sun Management Center agents. Some advanced hardware-specific Sun Management Center modules, however, are not supported on all Sun hardware. Specifically, the platform Config-Reader and Dynamic Reconfiguration modules provide advanced management of the underlying hardware platform. The functions these modules provide are not necessarily applicable to all hardware systems in the Sun product family.

The following table summarizes the availability of the Sun Management Center management modules on the various hardware platforms.

TABLE C-2 Hardware-Specific Module Availability

Hardware	Config-Reader Module	Dynamic Reconfiguration Module	All Other Sun Management Center Modules
SPARCStation 1, 2, 5, 10, 20	No	No	Yes
Sun Ultra 1, 450	Yes	No	Yes
Sun Enterprise 5, 10, 150, Sun Fire 280R, Sun Fire V480	Yes	No	Yes
SPARCserver 1000, 1000E	Yes	No	Yes
SPARCcenter 2000, 2000E	Yes	No	Yes
Sun StorEdge A5x00, T3	Yes	No	Yes
Netra T1120-1125, T1400-T1405	Yes	No	Yes
Sun Blade 100, 1000, 1500, 2500	Yes	No	Yes

TABLE C-2 Hardware-Specific Module Availability (Continued)

Hardware	Config-Reader Module	Dynamic Reconfiguration Module	All Other Sun Management Center Modules
Sun Fire 3800, 4800, 4810, 6800, V210, V240, V250, V440, V880, E25K, E20K, E6900, E4900	Yes	Yes	Yes

Management Module Resources

The resource requirements of management modules depend on the following factors:

- The number of managed properties in the module.
- The volume of managed property data processed in the module. Tables with many rows of data incur increased resource usage.
- The refresh intervals of managed properties.
- The complexity of data collection and rule processing.

The following table summarizes the resource impact of the Sun Management Center management modules.

TABLE C-3 Sun Management Center Management Module System Impact Summary

Module	Impact
Agent Statistics	Incurs low footprint increase and low CPU load increase.
Config-Reader	Uses CPU and memory relative to the complexity of the hardware configuration of the managed node.
Data Logging Registry	Incurs low footprint and CPU load increase that is proportional to the amount of data values being logged.
Directory Size Monitoring	Incurs a low footprint increase that is proportional to the number of directories monitored. Incurs low to moderate CPU load that depends on both the number of directories monitored and the activity within those directories.
Dynamic Reconfiguration	Has minimal footprint impact and utilizes CPU only when performing reconfiguration operations.

TABLE C-3 Sun Management Center Management Module System Impact Summary
(Continued)

Module	Impact
File Monitoring	Incurs low footprint increase proportional to the number of files that are monitored. Incurs low to moderate CPU load, depending on both the number of files that are monitored and the activity within those files.
File Scanning (System Log)	Incurs low footprint and CPU load increase.
Health Monitoring	Has relatively low impact on resources.
HP JetDirect	Incurs low footprint increase and low CPU load.
IPV6 Instrumentation Module	Incurs low CPU load increase and low to medium footprint increase dependent on the number of network interfaces.
Kernel Reader, Full	Affects CPU and memory based on the number of file systems, CPUs, and other system resources under management, as well as the rate of refresh of this information. Consumes more resources than the Simple Kernel Reader.
Kernel Reader, Simple	Has minimal impact on CPU and memory.
MIB-II Instrumentation	Incurs minimal CPU load and low to moderate footprint increase depending on the number of network interfaces, and the size of the routing tables, ARP tables, and related system tables.
MIB-II Proxy Monitoring	Incurs moderate footprint increase proportional to the size of the MIB of the proxy-monitored SNMP agent. Incurs low to moderate CPU load proportional to the number of managed objects in the proxy-monitored SNMP agent.
MIB-II Simple	Incurs virtually no CPU load and very little footprint increase, proportional to the size of the system interfaces, IP forwarding, and IP address table.
NFS File System	Incurs low footprint increase that is proportional to the number of network file systems mounted on the host machine, and low CPU load.
NFS Statistics	Incurs low footprint increase and low to moderate CPU load.
Print Spooler	Incurs low footprint and CPU load increase.

TABLE C-3 Sun Management Center Management Module System Impact Summary
(Continued)

Module	Impact
Solaris Process Monitoring	Incurs low footprint increase that is proportional to the number of processes monitored. Incurs low to moderate CPU load, depending both on the number of processes monitored and how often the processes are started and stopped.
Sun StorEdge A5x00 Array, Sun StorEdge T3 Array	Incurs moderate footprint and load increase that is proportional to the size of the storage device.

Server Layer Resources

The server layer is the core of the Sun Management Center software. The specification of appropriate hardware for the server layer host is critical to ensure the reliable and responsive operation of Sun Management Center. The hardware requirements for the Sun Management Center server layer are significantly greater than the requirement for agents. Sun Management Center 3.6 server layer system requirements are greater than the hardware requirements for Sun Management Center 2.x and 3.0 server layers. Version 2.x or 3.0 server hosts do not necessarily meet the Sun Management Center 3.6 system requirements.

The Sun Management Center server layer is supported on SPARC platform desktops and servers running on Solaris version 8, version 9, or version 10, that meet the minimum hardware requirements described in this section.

Note – For the best performance, install the Sun Management Center 3.6 server layer on a dedicated machine running server layer applications only.

Recommended Server Hardware Platforms

The hardware systems specified in the following table represent four broad classes of machines that can be employed as Sun Management Center server platforms. In each case, alternate machine configurations could provide equivalent performance.

TABLE C-4 Recommended Sun Management Center Server Hardware Platforms

Architecture	Machine Type	CPU Type	RAM	Swap Space
Small server	Sun Blade 100 or equivalent	One 502 MHz UltraSPARC IIe CPU or better	1 Gbyte	512 minimum, 1 Gbyte recommended
Medium server	Sun Fire 280R	Two 750 MHz UltraSPARC II CPUs or better	1 Gbyte	512 minimum, 1 Gbyte recommended
Large server	Sun Blade 2000	Two 1015 Mhz UltraSPARC III CPUs or better	1 Gbyte	512 minimum, 1 Gbyte recommended
Extra-large server	Sun Fire 880	Four 900 Mhz UltraSPARC III CPUs or better	2 Gbytes	1 Gbyte

Sizing Requirements

The Sun Management Server host sizing requirements are highly dependent on the number of agents being managed by the server layer and the management activity on these agents. Management activity consists of system-generated activity such as event generation and processing, and user-initiated operations such as browsing data, network discovery, group operations, and system monitoring and diagnosis.

Because of the impact of management activity, the sizing requirements depends on the number, type and configuration of all Sun Management Center add-on packages that are installed on the server, and on the number of managed nodes. In general, the more add-ons that are in use, the greater the management activity and the higher the server hardware requirements.

The following diagram shows the machine classes recommended for the Sun Management Center server as a function of the number of agents under management, and the estimated management activity. The diagram assumes that Sun Management Center consoles are not running on the server machine. The diagram also assumes that there are 5 remote console sessions for the small server; 10 remote console sessions for the medium server; and 15 remote console sessions for the large and extra large server.




FIGURE C-1 Sun Management Center Server Load by Events per Day and Objects Managed

The machine classes depicted in the above diagram are representative of classes of hosts with similar performance.



Caution – Server performance is adversely affected by running the Sun Management Center console application on the server layer host and by the number of active console sessions. If the server host is not sized generously to support the server layer components, do not run Sun Management Center consoles on the server machine.

Sun Management Center Server with the Performance Reporting Manager Add-on

The Sun Management Center performance reporting manager (PRM) add-on is used to track historical trends and generate reports for any data property being monitored by Sun Management Center agents. The PRM add-on can have a significant impact on the sizing requirements of the Sun Management Center server since it can involve the collection and processing of large volumes of data.

The impact of the PRM add-on is shown in the PRM segment of [Figure C-1](#). In general, increasing the management activity and the total number of data properties being tracked by PRM reduces the number of agents that can be managed by the Sun Management Center server.

Determining the requirements for a Sun Management Center server with the PRM add-on requires two steps.

1. Based on the total number of agents to be managed by Sun Management Center server with the PRM add-on installed, refer to the PRM segment of [Figure C-1](#) to determine the required machine class.
2. Based on the estimated number of PRM data properties you want to collect, determine the appropriate PRM configuration as described in the following section.

PRM Configuration Types

During Sun Management Center setup, you are given the option to select one of the PRM configuration types shown in the following table. The architecture column refers to the machine architecture listed in [Table C-4](#).

TABLE C-5 PRM Configuration Type Requirements

PRM Configuration Type	Disk Space	Total Number of PRM Properties	Example Number of agents	Example Number of properties per agent	Architecture
Small PRM	5 Gbytes	50,000	100	300	Small
			400	100	Medium
Medium PRM	12 Gbytes	150,000	300	300	Medium
			500	300	Large
			750	200	Extra large
Large PRM	24 Gbytes	240,000	600	300	Large
			750	300	Extra large

Small Sun Management Center servers are typically used for a small PRM configuration; medium servers are used for a medium PRM configuration; and large and extra large servers are used for a large PRM configuration. You can use an extra large Sun Management Center server with a small or medium PRM, depending on the available disk space and anticipated PRM data collection requirements.

PRM Server Configuration Examples

The following table provides examples of the numbers of agents that can be managed by each architecture type, assuming that each agent is collecting an average of 300 properties each for PRM. The Hourly Data Collection provides the estimated time required to collect data. The Nightly Processing column provides the estimated time to process the collected data. The duration of the data collection and subsequent processing depends on the server hardware, the server activity, and the amount of PRM data in the database.

TABLE C-6 Server Examples: Number of Agents under Management

Architecture	Number of Agents	Total Number of PRM Properties	PRM Configuration Type	Hourly Data Collection	Nightly Processing
Small	100	30,000	Small	2 minutes	1 to 2 hours
Medium	300	90,000	Medium	7 minutes	3 to 4 hours
Large	600	180,000	Large	7 minutes	3 to 6 hours
Extra large	750	225,000	Large	6 minutes	3 to 6 hours

Generating Performance Reporting Manager Reports

A wide range of reports can be generated by specifying different numbers of agents, numbers of data properties, and report durations such as 4 hours to 1 month.

Typical reports take a few seconds to several minutes to generate. The actual time required is affected by the following factors:

- The number of actual data points included in the report

Note – Reports are limited to a maximum of 10,000 data points per report.

- Amount of performance reporting manager data in the database
- Server performance and activity
- Concurrent generation of other performance reporting manager reports

For example, on a medium Sun Management Center server configured with the performance reporting manager add-on, a relatively simple report that includes 5 properties for 1 agent over the last 24 hours can be generated in about 20 seconds. Conversely, a more substantial report that includes 5 properties for 5 agents over the last 7 days can take around 10 minutes to generate.

Note – A medium Sun Management Center server with the performance reporting manager add-on is assumed to be a SunFire-280R with two 450 MHz UltraSPARC II CPUs, 1 GB RAM, and 1 GB swap. It is also assumed that the SunFire-280R is monitoring 300 agents and collecting 300 data properties per agent for the performance reporting manager.

Scheduling Performance Reporting Manager Reports

If a report takes more than 30 minutes to generate, it is recommended that you schedule the report to run between 4:00 AM and 8:00 AM. Scheduling large reports to run after 4:00 AM reduces the load on the Sun Management Center server during normal business hours, and also can reduce the chance of conflicts with the nightly Sun Management Center and performance reporting manager tasks that typically occur between 12:00 AM and 4:00 AM.

Performance Considerations

Major factors that affect the server layer performance include:

- Simultaneous startup of Sun Management Center components
- Topology group configuration
- Management activity
- Number of console users

Simultaneous Startup of Sun Management Center Components

Simultaneous startup of the server layer and many agents can adversely affect server layer performance. The initialization of a server layer managing hundreds of agents can result in slow console response and the temporary inability to access some agents.

Topology Group Configuration

The number of topology groups in a Sun Management Center server context should not exceed the following:

- Small servers - 25 topology groups
- Medium servers - 50 topology groups
- Large servers - 75 topology groups
- Extra-large servers - 100 topology groups

The maximum number of immediate child objects in a topology group is 256. For optimal performance, the number of child objects in a group should not exceed 100.

If you install the Performance Reporting Manager add-on, each topology domain should contain less than 200 Sun Management Center agents to ensure optimal collection of Performance Reporting Manager data.

Management Activity

Sun Management Center server activity depends on the following factors:

- The number of operations initiated by users
- The stability and activity of the host systems under management
- The number of management modules loaded by the host systems
- The specification of alarm thresholds and rule parameters for properties under management

The last two factors greatly influence the tendency of the managed nodes to generate management activity in the form of event processing.

As a result, high management activity can occur with no add-ons if alarm thresholds are poorly configured. Conversely, low management activity can occur with many add-ons if the managed systems are stable and the alarm thresholds are reasonable.

Number of Console Users

Increasing the number of concurrent Sun Management Center console user sessions incurs a modest increase in load on the server layer. The sizing estimates assume 5 active users for a small configuration, 10 users for a medium configuration, and 15 users for a large and extra-large configuration. The sizing estimates assume the users are performing activities such as browsing managed property data and events and editing property attributes.

Some user-initiated actions might temporarily affect the performance of the server layer for the duration of the operation.

- **Large group operations** that are targeted at 100 or more agents can consume significant server resources. These operations can further affect server performance if the changes generate alarms on the managed agents. These alarms produce additional management activity in the form of event processing.
- **Network discovery operations** involving the addition of many new entities for the server to manage can incur noticeable load on the server layer host during the discovery process.
- **Topology data import operations** involving the addition of many new entities to manage can result in slower response from the server layer while the entities are being added.

The effect of these user-initiated actions can be minimized by not executing these operations concurrently, by breaking up large operations, and, when possible, by performing or scheduling the operations during off-peak hours.

Java Console Layer Resources

For the best performance, the Sun Management Center console should be run from a host other than the server layer host. The console can be readily installed on any host and used to connect to the server layer remotely. The recommended server layer configurations assume that the host system is dedicated to running server layer applications only. Running other applications such as the Sun Management Center console on the server layer host should be avoided unless the server host has been sized generously to support the additional requirements.

The Sun Management Center console is based on the Java technology. The console is supported on SPARC systems running the Solaris 2.6, Solaris 7, Solaris 8, Solaris 9, or Solaris 10 operating systems and x86 systems running Solaris 9 and Solaris 10. The console is also supported on Intel systems running Microsoft Windows 2000, Microsoft Windows NT 4.0 with Service Pack 3 or 4, Microsoft Windows 98, and Microsoft Windows XP.

Sun Fire Proxy/Platform Agent Resources

Sun Fire platform agents require a different installation procedure than standard Sun Management Center agents. Sun Fire platforms contain a number of domains, each domain with its own hardware allocation. Each domain runs a separate Solaris operating environment instance. Each of the Sun Fire domains runs a domain agent.

The Sun Fire platform as a whole consists of all the hardware in the platform allocated to the domains. The platform is controlled by a System Controller (SC) board within the platform.

To manage Sun Fire servers, Sun Management Center software uses Sun Fire platform agents that interact with the Sun Fire server system controller and Sun Fire domain agents. The platform agents must be deployed on a Solaris host external to the Sun Fire chassis that the agents are to monitor. Multiple platform agents can be deployed on a single host system to manage multiple Sun Fire servers, provided that the platform agent host system has been sized accordingly.

On average, each platform agent consumes 5% to 9% CPU and 15 to 18 Mbytes of memory. The CPU and memory consumption of platform agents deployed on the same host system are additive and can be used to gauge hardware requirements. The disk space requirements for multiple platform agent instances are minimally more than that for a single platform agent instance because the agents share the same software packages.

In general, the CPU and memory resource requirements of a platform agent are proportional to the size and complexity of the Sun Fire server configuration being managed. Sun Fire systems with larger configurations require more platform agent resources on the platform agent host.

System Requirements

You can install platform agents on either:

- A Sun Management Center server layer host
- A Sun Management Center dedicated platform agent host

The number of platform agents that can be installed on a given host varies depending on whether that host is a Sun Management Center server layer or platform agent layer host. To maximize the overall performance and responsiveness of Sun Management Center, platform agents should be deployed on dedicated hosts instead of the server layer host. If the server layer is deployed on a multiple CPU system with excess capacity, you can consider running platform agents on a server layer host.

The following figure shows the architecture for a dedicated platform agent host deployment, and a server layer host deployment.




FIGURE C-2 Platform Agent Architecture

Startup of Multiple Platform Agents

Sun Fire platform agents refresh their management information hourly by default. When multiple platform agents are deployed on the same host and are initialized at the same time, the agents tend to perform their data refreshes in quick succession. If too many platform agents attempt to refresh their data concurrently, the overall responsiveness of the host system can be adversely affected.

To reduce the likelihood of concurrent operations by multiple platform agents on the same host, do not start all of the platform agents at the same time.

Deploying Sun Fire Platform Agents on a Dedicated Host

The following table lists typical hardware configurations and the corresponding number of platform agents that can be deployed on the dedicated host system.

TABLE C-7 Dedicated Host: Sun Fire Platform Agent Capacity

Representative Hardware Configurations	Maximum Number of Platform Agents
Sun Blade 100 with a single 500 MHz UltraSPARC IIe CPU, 1 Gbyte of RAM and 1 Gbyte of swap	5 to 7

TABLE C-7 Dedicated Host: Sun Fire Platform Agent Capacity (Continued)

Representative Hardware Configurations	Maximum Number of Platform Agents
Sun Fire 280R, Netra T4, or Sun Blade 1000 with dual 750 MHz UltraSPARC III CPUs, 1 Gbyte of RAM, and 1 Gbyte of swap	14 to 20

Because platform agent resource use can vary, the limits shown in the table represent a range of acceptable values that leave sufficient capacity to ensure that operational peaks do not exhaust system capacity. Larger Sun Fire platforms require greater platform agent resources, with the result that fewer platform agents can be run on a single host. Conversely, smaller Sun Fire platforms require fewer platform agent resources, so more platform agents can be run on a single host.

Deploying Sun Fire Platform Agents on a Server Layer Host

The hardware sizing requirements of a host system running the Sun Management Center server layer are a function of the number of platform agents managed by the server layer and the management activity in the system.

Only large multiple-CPU systems should be considered for running both the Sun Management Center server layer and Sun Fire platform agents. The deployment of platform agents on a server layer host with limited capacity can adversely affect the overall performance of Sun Management Center.

Assuming a moderate level of management activity of fewer than 1000 events per host per day, the maximum number of platform agents that can be deployed on a Sun Management Center server layer host is the function of the number of agents under management and the machine class. The following table lists typical system capacity.

TABLE C-8 Server Layer Host: Sun Fire Platform Agent Capacity

Number of Agents Under Management	Maximum Number of Platform Agents
100	6
300	5
500	4
750	NA

Sun Fire 280R denotes a Sun Fire 280R, a Sun Blade 1000, or a Netra T4 system with a dual 750 MHz UltraSPARC III server host with 1 Gbyte of RAM and 1 Gbyte of swap.

For Sun Fire Sun Management Center installation procedures, see *Sun Management Center Software Supplement for Sun Fire 6800/4810/4800/3800 Systems*.

Network Address Translation

This appendix describes the issues related to using Sun Management Center 3.6 in a NAT environment, and outlines the factors that affect the overall approach to a Sun Management Center NAT solution.

This chapter discusses the following topics.

- “NAT Concepts” on page 257
- “Complexity of the NAT Solution” on page 259
- “NAT Configuration” on page 260
- “NAT Solution” on page 261
- “NAT Limitations” on page 261
- “NAT Examples” on page 262

NAT Concepts

Network Address Translation (NAT) enables servers, hosts, and consoles on different networks to communicate with each other across a common internal network. A NAT solution maps the private local address realm to a public address realm. These mappings can be static or dynamic.

NAT is becoming increasingly prevalent in Sun Management Center client environments. By using NAT, clients can make more efficient use of network addresses and, in some cases, provide secure access to external networks from sensitive internal environments.

Note – The term *Sun Management Center NAT host* refers to any host that is running a Sun Management Center component (agent, server, or console) and that must communicate with other Sun Management Center components across a NAT environment.

Use of IP Addresses With NAT

Sun Management Center 3.6 assumes that the IP address and port of a managed node can be used to uniquely identify and access the managed node within a server context. Furthermore, the software assumes that the local IP address and port of a managed node are authoritative.

As a result of these assumptions, Sun Management Center makes extensive use of IP addresses in both its core operation and its management functionality. Specifically, network addresses are used in the following areas:

- Communication (SNMP, RMI, Probe, MCP HTTP, ICMP)
- Network entity discovery
- Event management
- Identifying server contexts
- Identifying managed nodes, objects, and properties using SNMP URLs
- Managing property contents, for example, the MIB-II module
- Managed property table indices, for example, the MIB-II interfaces table
- Generating localized USEC keys
- Various console browsers and displays

In environments where Sun Management Center components operate across one or more NAT environments, the assumptions regarding the uniqueness and accessibility of the local IP addresses and ports of managed nodes break down. Furthermore, because administrators might be more familiar with the node's public IP address, the use of local IP addresses to identify managed nodes in a NAT environment might no longer be intuitive.

How NAT Works

The following figure illustrates how NAT works.




FIGURE D-1 Simple NAT Network Conceptual Diagram

The private subnet 10.1.1.0 has one machine called Machine 1 that runs behind NAT 1, which uses 129.146.63.100, a translated IP address, for all communication from Machine 1 to hosts outside NAT 1. Communication from hosts outside NAT 1 to Machine 1 (129.146.63.100) are redirected to Machine 1 (10.1.1.1) by NAT 1.

A second private subnet (100.1.1.1) has one machine Machine 3 (100.1.1.1) and runs behind NAT 2, which uses 129.146.63.101 (a translated IP) for communication from Machine 3 to hosts outside NAT 2. Communication from hosts outside NAT 2 to Machine 3 (129.146.63.101) is redirected to 100.1.1.1 by NAT 2.

Complexity of the NAT Solution

The extensive use of IP addresses in Sun Management Center complicates deployment in environments that involve simple address or proxy translations. The addresses appear at the driver, library, application, and console integration levels. The solution is further complicated by the types of communication that occur in Sun Management Center.

This software is a distributed application with the following layers:

- Console
- Multicomponent server
- Multicomponent agent

The software layers can reside on a different host or on different networks that could be subject to routing rules or NAT.

Furthermore, the console, server, or agent components of one Sun Management Center system can potentially communicate with components of another Sun Management Center system on another network. These aspects add to the complexity of the solution.

NAT enables Sun Management Center 3.6 to operate in a network environment where the consoles, servers, and agents are deployed in one or more network addressing realms. As a result, the consoles, servers, and agents must communicate across one or more NAT environments.

The functionality also supports cross-server context operation such as remote reference domains across NAT environments. With NAT, Sun Management Center components can also communicate with other Sun Management Center components in the same addressing realm. Without NAT, Sun Management Center consoles, servers and agents cannot operate across NAT environments.

NAT Configuration

Static NAT mappings must be defined for every Sun Management Center NAT host.

Note – Dynamic NAT mappings are not supported for Sun Management Center 3.6 operation across the NAT.

Because several undefined ports are used by Sun Management Center, Sun Management Center does not support the ability to specify port restrictions for Sun Management Center NAT support. These ports include SNMP, probe, RMI, and console integration.

To support operation in a NAT environment, NAT enables Sun Management Center 3.6 software to use names rather than IP addresses to identify and communicate with other Sun Management Center hosts. The name must be a host alias that can be resolved to a valid IP address through standard naming services. This name also must be resolvable to the appropriate IP address in the relevant addressing realms in which the Sun Management Center components are deployed.

Thus, common host aliases for all Sun Management Center NAT hosts must be defined in the host maps of all addressing realms in which Sun Management Center components are installed.

The host aliases must be defined in the standard system host maps that can include such things as the files, for example, `/etc/hosts`, NIS, NIS+, and DNS. For the remainder of this chapter, the common host alias is referred to as the NAT host name.

NAT Solution

The Sun Management Center NAT solution is focused on self-consistency to avoid complex or error-prone translation mechanisms. This solution addresses the fundamental assumption regarding the use of IP addresses in the software.

Sun Management Center 3.6 uses logical identifiers, rather than IP addresses, to uniquely identify and access the nodes managed by the software in NAT environments. The identifiers can be the fully qualified host name of a managed node. This method enables Sun Management Center 3.6 to leverage the existing host name-to-IP address mapping infrastructure in IP-based systems.

In environments where the use of fully qualified host names are not appropriate or feasible, any logical name that is unique and resolvable from the agent and server layer addressing realm can be used. In non-NAT environments, the logical identifiers can default to IP addresses for backward compatibility.

This solution requires that the logical identifier must be unique within a server context. The logical identifiers must be resolvable to valid IP addresses that can be used to access the managed node across a NAT environment. You should be able to use the logical identifiers to intuitively identify managed nodes.

When using the Sun Management Center 3.6 NAT solution, note the following information:

- Static NAT mappings must be specified for all Sun Management Center NAT hosts.
- Host map entries must be specified for all NAT hosts in all the network addressing realms in which Sun Management Center components are deployed.
- Routing table-based discovery using more than one hop is not supported across NAT environments.
- A console deployed behind a NAT does not work with a server outside the NAT.

NAT Limitations

The following NAT limitations exist:

- The IP address should be unique for Sun Management Center servers and Sun Management Center agent hosts.
- The host name should be unique to Sun Management Center hosts. If the host name is not unique, you will have flexibility to choose the host alias during the software setup.

- If Sun Management Center server is set up using NAT, the host name or host alias must not contain dashes. For example, do not use `server-one` for the name of a Sun Management Center server if the server is set up using NAT.
- Running the console on hosts behind NAT and running the server outside of NAT is not supported.

NAT Examples

This section provides examples of a single NAT environment and a dual NAT environment.

Single NAT Environment

The basic NAT example involves a single NAT environment where a single server context is deployed on both sides of the NAT.




FIGURE D-2 Simple NAT Network Configuration Example

The figure shows the console, a server layer, and an agent deployed in the 192.168.0.0 network. A console and three agents are deployed in the 192.168.1.0 network behind the NAT. All of the agents, including the remote agents, are part of the server context managed by the server layer on Host B.

Sun Management Center assumes that these components are configured to operate in the host name logical addressing mode. Therefore, all agents are configured with Host B as their trap and event destinations.

To support this configuration, the network host and NAT maps listed in [Figure D-2](#) must be complete. The three remote agents on Hosts E, F, and G are accessible from the 192.168.0.0 network using static NAT mappings. Furthermore, the logical identifiers of Hosts E, F and G must also be resolvable to valid IP addresses in the 192.168.0.0 network. This step is accomplished through the host mappings for Hosts E, F, and G in the 192.168.0.0 network.

To allow the remote agents to name Host B as their trap and event destinations, a host map entry for Host B is specified in the 192.168.1.0 network host map.

Dual NAT Environment

The following figure illustrates a more complex example. The figure shows a dual NAT environment with three Sun Management Center server contexts with remote reference domains.




FIGURE D-3 Complex NAT Network Configuration Example

In the figure, the 192.168.0.0 network is in front of the NAT environments, while the 192.168.1.0 and 192.168.2.0 networks are behind the NAT environments. SunScreen 1 provides the 192.168.0.0 network with access to hosts on the 192.168.1.0 network. SunScreen 2 provides the 192.168.0.0 network with access to hosts in the 192.168.2.0 network. Static NAT mappings are assumed.

Host maps in the three addressing realms provide host name resolution for all hosts on which Sun Management Center server and agent components are deployed. All Sun Management Center components are assumed to have been configured with the host name logical addressing mode.

Sun Management Center 3.6 Packages

This appendix provides a list of the Sun Management Center packages and descriptions.

Package Name	Description
<i>Packages for ELP Config-Reader</i>	
SUNWescns	Sun Management Center Common Config Reader Module Server Netra 440 Platform Component
SUNWescna	Sun Management Center Common Config Reader Module Netra 440 Agent Component
SUNWescnl	Sun Management Center Common Config Reader Netra 440 Platform Support
SUNWesona	Sun Management Center Common Config Reader Module Sun Fire T2000 Agent Component
SUNWesonl	Sun Management Center Common Config Reader Sun Fire T2000 Platform Support
SUNWesons	Sun Management Center Common Config Reader Module Sun Fire T2000 Platform Component
SUNWespda	Sun Management Center Common Config Reader Module Agent PCPDAQ Component
SUNWespdli	Sun Management Center Common Config Reader PCPDAQ Library
SUNWescci	Sun Management Center Common Config Reader Module Initialization
SUNWesccs	Sun Management Center Common Config Reader Module Server Core Component

Package Name	Description
SUNWescca	Sun Management Center Common Config Reader Module Agent Core Component
SUNWescda	Sun Management Center Common Config Reader Module DAQ Component
SUNWescdl	Sun Management Center Common Config Reader DAQ Library
SUNWescps	Sun Management Center Common Config Reader Module Sun Fire V210/V240 and Netra 240 Server Component
SUNWescpa	Sun Management Center Common Config Reader Module Sun Fire V210/V240 and Netra 240 Agent Component
SUNWescpl	Common Config Reader Module Sun Fire V210/V240 and Netra 240 platform support
SUNWescfs	Sun Management Center Common Config Reader Module Sun Fire V250 Server Component
SUNWescfa	Sun Management Center Common Config Reader Module Sun Fire V250 Agent Component
SUNWescfl	Common Config Reader Module Sun Fire V250 platform support
SUNWeschs	Sun Management Center Common Config Reader Module Sun Fire V440 Server Component
SUNWescha	Sun Management Center Common Config Reader Module Sun Fire V440 Agent Component
SUNWeschl	Common Config Reader Module Sun Fire V440 platform support
SUNWescws	Sun Management Center Common Config Reader Module Sun Blade 1500/2500 Server Platform Component
SUNWescwa	Sun Management Center Common Config Reader Module Sun Blade 1500/2500 Agent Platform Component
<i>Packages for Sun Fire Entry-level Midrange Systems</i>	
SUNWeslw8s	Sun Management Center Server Images For Sun Fire Entry-Level Midrange System Platform
SUNWeslw8a	Sun Management Center Config Agent For Sun Fire Entry-Level Midrange System Platforms
SUNWeslw8c	Sun Management Center Sun Fire Entry-Level Midrange System Installation Scripts
<i>Packages for Sun Fire Midrange Systems</i>	
SUNWensda	Sun Management Center Sun Fire 6800-3800 Domain Agent English Messages

Package Name	Description
SUNWessco	Sun Management Center Sun Fire 6800-3800 Support - Server component for Domain Admin Module
SUNWesssd	Sun Management Center Server server-side files for Sun Fire 6800-3800 Domain
SUNWedacs	Sun Management Center Sun Fire 6800-3800 Domain Admin module Setup for Server and Agent
SUNWessda	Sun Management Center Sun Fire 6800-3800 Domain Agent
<i>Packages for Hardware Diagnostic Suite</i>	
SUNWedagx	64-bit Hardware Diagnostic Suite Agent and Tests
SUNWjaedp	Japanese Localization for Hardware Diagnostic Suite properties files
SUNWkoedh	Korean Localization for Hardware Diagnostic Suite Help and Image files
SUNWkoedp	Korean Localization for Hardware Diagnostic Suite properties files
SUNWedag	Hardware Diagnostic Suite Agent and Tests
SUNWenedh	Hardware Diagnostic Suite Help and Image files
SUNWenedp	English Localization for Hardware Diagnostic Suite Server and UI
SUNWfredh	French Localization for Hardware Diagnostic Suite Help and Image files
SUNWfredp	French Localization for Hardware Diagnostic Suite properties files
SUNWhdrmi	Hardware Diagnostic Suite Server and UI
SUNWhedh	Traditional Chinese Localization for Hardware Diagnostic Suite Help and Image files
SUNWhedp	Traditional Chinese Localization for Hardware Diagnostic Suite properties files
SUNWjaedh	Japanese Localization for Hardware Diagnostic Suite Help and Image files
SUNWcedh	Simplified Chinese Localization for Hardware Diagnostic Suite Help and Image files
SUNWcedp	Simplified Chinese Localization for Hardware Diagnostic Suite properties files
SUNWed	Hardware Diagnostic Suite Server and UI
SUNWedcom	Hardware Diagnostic Suite common components among server and agent installations
SUNWedh	English help files for Hardware Diagnostic Suite

Package Name	Description
<i>Packages for Advanced Monitoring</i>	
SUNWessmn	Sun Management Center Advanced Server Monitoring add-on
SUNWespro	Sun Management Center Process Module for advanced monitoring pack
SUNWesip6	This package provides IPV6 modules for advanced monitoring pack
SUNWenadm	Sun Management Center Advanced Monitoring message files package
SUNWesamn	Sun Management Center Advanced Monitoring Pack Modules
SUNWescam	Sun Management Center Advanced Monitoring add-on console component
SUNWesfma	Sun Management Center Fault Management Architecture (FMA) module of Advanced System Monitoring add-on. This package is available only on Solaris 10.
SUNWeshds	Sun Management Center Volume System Monitoring (VSM) module.
SUNWessmf	Sun Management Center Service Management Facility (SMF) module of Advanced System Monitoring add-on. This package is available only on Solaris 10.
<i>Packages for Desktop/Workstations</i>	
SUNWeswsi	Sun Management Center Ultra Workstation Initialization
SUNWeswss	Sun Management Center Server Images For Ultra Workstations
SUNWeswsa	Sun Management Center Configd Agent For Ultra Workstations
<i>Packages for Service Availability Manager</i>	
SUNWescs	Service Availability Manager console layer support for Sun Management Center Console
SUNWeshes	Service Availability Manager Help package for Sun Management Center
SUNWessam	Service Availability Manager add-on for Sun Management Center
SUNWesses	Service Availability Manager server-side interface component for Sun Management Center Server
SUNWesaes	Service Availability Manager add-on for Sun Management Center agent
<i>Packages for Netra</i>	
SUNWesnti	Sun Management Center Netra T Installation Scripts
SUNWesnts	Sun Management Center Server Images For Netra t Platforms

Package Name	Description
SUNWesnta	Sun Management Center Configd Agent For Netra t Platforms
<i>Packages for Performance Reporting Manager</i>	
SUNWesarg	Sun Management Center Performance Reporting Manager add-on agent package
SUNWescrg	Sun Management Center Performance Reporting Manager console layer support package
SUNWeshrg	Sun Management Center Performance Reporting Manager help package
SUNWeslrg	Sun Management Center Performance Reporting Manager Service API (client-side) package
SUNWesprm	Sun Management Center Performance Reporting Manager add-on
SUNWessrg	Sun Management Center Performance Reporting Manager server layer support package
SUNWesdr	Sun Management Center Performance Reporting Manager database package
<i>Packages for Dynamic Reconfiguration on Sun Fire</i>	
SUNWensdr	Sun Management Center -- Sun Fire 15K-3800 Dynamic Reconfiguration English Messages
SUNWescd	Sun Management Center Sun Fire 15K-3800 Support - Console component for Dynamic Reconfiguration
SUNWescdf	Sun Management Center console support for Dynamic Reconfiguration on Sun Fire 15K-3800 platforms
SUNWessdf	Sun Management Center server support for Dynamic Reconfiguration on Sun Fire 15K-3800 platforms
SUNWesadf	Sun Management Center agent support for Dynamic Reconfiguration on Sun Fire 15K-3800 platforms
<i>Packages for Platform Administration</i>	
SUNWenspa	Sun Management Center -- Sun Fire Platform Agent English Messages
SUNWescp	Sun Management Center Sun Fire 6800-3800 Support - Console component for Platform Administration Module
SUNWesp	Sun Management Center Sun Fire 6800-3800 Support - Server component for Platform Administration Module
SUNWesspc	Sun Management Center Console Sun Fire Platform Administration

Package Name	Description
SUNWessps	SunMC Server Support Package For Sun Fire Platform Administration
SUNWesspa	Sun Management Center -- Sun Fire Platform Agent functionality for Sun Fire 6800-3800 Systems
<i>Packages for Storage Module</i>	
SUNWenstm	Sun Management Center - Storage Modules message files package
SUNWesstg	Sun Management Center Storage Modules GUI Setup
SUNWessts	SunMCR Support Package For Storage Modules
SUNWessta	SunMC Agent Support Package For Storage Modules
<i>Packages for Sun Fire High-End Systems</i>	
SUNWesscs	Sun Management Center Sun Fire 15K/12K Server Support
SUNWscscs	Sun Management Center Sun Fire 15K/12K System Controller Server Support
SUNWensca	Sun Management Center Sun Fire 15K/12K English Message Files
SUNWesscd	Sun Management Center Sun Fire 15K/12K Domain Agent Support
SUNWesscg	Sun Management Center Sun Fire 15K/12K Common Support
SUNWesscp	Sun Management Center Sun Fire 15K/12K Platform Agent Support
SUNWscsca	Sun Management Center Sun Fire 15K/12K System Controller Agent Support
<i>Packages for System Reliability Manager</i>	
SUNWesasm	Sun Management Center System Reliability Manager Modules
SUNWeshsm	Sun Management Center System Reliability Manager Help
SUNWessrm	Sun Management Center System Reliability Manager message files package
SUNWesssm	Sun Management Center System Reliability Manager - Server layer support
<i>Packages for Unicenter TNG Integration</i>	
SUNWencam	Sun Management Center - Unicenter TNG Integration message files package
SUNWescaa	Sun Management Center - Unicenter TNG Integration event adaptor package
SUNWescad	Sun Management Center - Unicenter TNG Integration DSM package

Package Name	Description
SUNWescah	Sun Management Center - Unicenter TNG Integration hostDetailBean package
SUNWescas	Sun Management Center - Unicenter TNG Integration world view package
SUNWescap	Sun Management Center - Supporting package for Unicenter TNG Integration event adaptor package
<i>Packages for Tivoli Integration</i>	
SUNWentia	Sun Management Center - Tivoli Integration message files package
SUNWestia	Sun Management Center - Tivoli TEC integration
<i>Packages for Workgroup Server</i>	
SUNWeswgi	Sun Management Center Workgroup Server Initialization
SUNWeswgs	Sun Management Center Server Layer support for Workgroup Servers
SUNWeswga	Sun Management Center Workgroup Server Agent Support libraries
SUNWeswha	Sun Management Center Workgroup Server Agent Support libraries
SUNWeswhd	Sun Management Center Workgroup Server Agent Support (V880 Specific) libraries
<i>Packages for Dynamic Agent Update</i>	
SUNWsuagt	Sun Management Center Dynamic Agent Update Agent Components and support files
SUNWsucon	Sun Management Center Dynamic Agent Update Console Components
SUNWsusrv	Sun Management Center Dynamic Agent Update Server Components
<i>Packages for Solaris Container Manager</i>	
SUNWscma	Solaris Container Manager Agent
SUNWscmc	Solaris Container Manager Console
SUNWscmca	Solaris Container Manager Client API
SUNWscmcm	Solaris Container Manager Common Components
SUNWscmdb	Solaris Container Manager Database
SUNWscmh	Solaris Container Manager Help
SUNWscmp	Solaris Container Manager Properties Files

Package Name	Description
SUNWscms	Solaris Container Manager Server
<i>Packages for Dynamic Agent Update</i>	
SUNWsuagt	Sun Management Center Dynamic Agent Update Agent Components and support files
SUNWsucon	Sun Management Center Dynamic Agent Update Console Components
SUNWsusrv	Sun Management Center Dynamic Agent Update Server Components
<i>Other Packages</i>	
SUNWenesf	Sun Management Center Console and server properties
SUNWenesh	Sun Management Center SES HTML Help
SUNWenesi	Sun Management Center Script Localization Messages
SUNWesae	Sun Management Center Agent System Files
SUNWesagt	Sun Management Center Agent
SUNWesasc	Sun Management Center Advanced Services Console
SUNWesaxp	Java API for XML Processing (JAXP) v1.1.3
SUNWescdv	Sun Management Center Console Dataview
SUNWescix	Sun Management Center console-side Import/Export
SUNWescli	Sun Management Center SES Command—Line Interface
SUNWesclt	Sun Management Center Client API
SUNWescon	Sun Management Center SES Console
SUNWesgui	Sun Management Center GUI Installation
SUNWesjp	Sun Management Center Additional Components. Contains all the dependent Java components that are required to run SES
SUNWesjrm	Sun Management Center Client API support classes
SUNWesmc	Sun Management Center MCP Console
SUNWesmdr	Sun Management Center MDR for Basic Pack
SUNWesmod	Sun Management Center Agent Modules that are optional for SES agent
SUNWessdk	SDK components for all Sun Management Center installations
SUNWessdv	Sun Management Center Advanced Services Server side interface component for Dataview Services

Package Name	Description
SUNWesse	Sun Management Center Server System Files for SES server
SUNWessms	Sun Management Center MCP Services
SUNWessrv	Sun Management Center SES Server component
SUNWessvc	Sun Management Center Advanced Services server side interface component
SUNWesval	Sun Management Center Validation Tool Components
SUNWesweb	Sun Management Center Web Console
SUNWmeta	Sun Management Center SES Metadata Agent
SUNWescom	Sun Management Center Common Components for SES installations
SUNWesken	Sun Management Center Kernel Reader Module for SES installations
SUNWesmcp	Sun Management Center Module Configuration Propagation
SUNWesmib	Sun Management Center MIB Instance Module for SES installations
SUNWesaem	Sun Management Center Event Module for Agent
SUNWesdb	Sun Management Center Database for running SES components
SUNWessa	Sun Management Center SES Server/Agent
SUNWtcatr	Tomcat Servlet/JSP Container (root)
SUNWtcatu	Tomcat Servlet/JSP Container
SUNWesora	Sun Management Center Database Management System
SUNWestbl	Sun Management Center Database
SUNWesclb	Sun Management Center Command-Line Interface For BatchMode
SUNWeshdl	Volume System Monitoring add-on for Sun Management Center
SUNWeslac	Sun Management Center Local Access
SUNWlgsmc	Sun Management Center Web Console Authorization plugin

The following table lists the Linux rpms.

RPM Name	Description
sun-symon-enesf	Sun Management Center Console properties
sun-symon-enesi	Sun Management Center Script Localization Messages

sun-symon-esagt	Sun Management Center Agent
sun-symon-esasc	Sun Management Center Advanced Services Console
sun-symon-esaxp	Java API for XML Processing (JAXP) v1.1.3
sun-symon-escdv	Sun Management Center Console Dataview
sun-symon-escix	Sun Management Center Import/Export
sun-symon-escli	Sun Management Center Command—Line Interface
sun-symon-esclt	Sun Management Center Client API
sun-symon-escom	Sun Management Center Common Components
sun-symon-escon	Sun Management Center Console
sun-symon-esgui	Sun Management Center GUI Installation
sun-symon-esjp	Sun Management Center Additional Components
sun-symon-esjrm	Sun Management Center Client API support classes
sun-symon-esken	Sun Management Center Kernel Reader Module
sun-symon-esmc	Sun Management Center MCP Console
sun-symon-esmcp	Sun Management Center Module Configuration Propagation
sun-symon-esmib	Sun Management Center MIB Instance Module
sun-symon-esmod	Sun Management Center Agent Modules
sun-symon-esval	Sun Management Center Validation Tool Components
sun-symon-suagt	Sun Management Center Dynamic Agent Update Agent Components
sun-symon-sucon	Sun Management Center Dynamic Agent Update Console Components

Index

A

- add-on products
 - additional add-ons, 50
 - base add-ons, 49
 - setting up a single product using
 - es-guisetup, 161-162
 - setting up a single product using
 - es-setup, 162
 - uninstalling using es-guiuninst, 209-210
 - uninstalling using es-uninst, 215
- add_to_install_server, JumpStart, 131
- administrators
 - definition of, 66
 - user name, 24
- Advanced System Monitoring, 49
 - disk space requirements, 28
 - operating system requirements, 28
 - port number, 184
- agent-update.bin, installing agents, 122
- agents, 48
 - assigning to a different server, 192-195
 - configuring on a multi-IP machine, 151-152
 - CPU and RAM use estimates, 240
 - creating agent-only installation image from CD, 119-121
 - creating update-image, 101
 - determining CPU resources for, 240-241
 - determining resources needed, 239-245
 - disk space requirements, 25, 26
 - example of heavy configuration, 241
 - example of light configuration, 241
 - handsfree installation, 122
 - installing using agent-update image, 122

agents (Continued)

- installing using JumpStart, 130
- JumpStart, creating base agent
 - image, 132-133
- operating system requirements, 25
- port number, default, 184
- port number, reconfiguring, 185
- security, 67
- Solstice Enterprise agent, 73
- SPARC, 239-245
- Sun Fire, 252-255
- system impact, 243
- update-image types, 103
- virtual memory, 242
 - x86, 240

architecture, 48

ASM, *See* Advanced System Monitoring

B

- backup, database and configuration data, 173
- base add-on products, 49
- base components, 48
- BMC Patrol, integrating with Sun Management Center, 201

C

- CD images, 85-87
- changing port addresses, 183-188
- checklist, preparing to upgrade or install, 74

- client to server, security, 68
 - commands
 - es-config options, 185-186
 - es-guiinst, graphical user interface
 - install, 29-32
 - es-guistart, graphical user interface
 - start, 166
 - es-guistop, graphical user interface
 - stop, 170
 - es-guiuninst, graphical interface
 - uninstall, 209-210
 - es-inst, command-line install, 217-218
 - es-setup, command-line set up and options, 229-230
 - es-start, command-line start, 167
 - es-stop, command-line stop, 171
 - es-uninst, command-line uninstall, 215
 - es-uninst options, 213-214
 - es-validate, check and verify installation, 162-164
 - netstat, to determine if port is in use, 184
 - community string, SNMP, 24
 - compatibility
 - Solstice SyMON 1.x, 73
 - Sun Enterprise SyMON, 74
 - Sun VTS, 73
 - Computer Associates Unicenter TNG, integrating with Sun Management Center, 201-203
 - configuration
 - backup, 173
 - considerations, 65-72
 - Performance Reporting Manager, 247-250
 - Performance Reporting Manager types, 248
 - restore, 177
 - configuration files, SNMP ports, 180
 - configuration manager, port number, 184
 - configuring
 - legacy agent as subagent, 181-183
 - network address translation, 260
 - port addresses, 183-188
 - Sun Management Center, 33-40
 - conflicting port addresses, 183-188
 - console
 - determining resources needed, 252
 - logging in automatically, 167
 - specifying heap size, 168
 - starting on Microsoft Windows, 169
 - console (Continued)
 - starting on Solaris, 168-169
 - system impact, 251-252
 - CPU resources
 - agent, 240-241
 - impact of console users, 251-252
 - large group operations, 251
 - large topology groups, 250
 - management activity, 251
 - network discovery operations, 251
 - simultaneous startup, 250
 - starting multiple Sun Fire platform agents, 254-255
 - Sun Fire platform agents, 253
 - topology data import operations, 251
 - creating a local zone, 40-41
 - cross-server communications, security, 67
 - cstservice, port number, 184
- D**
- data logging registry, system impact, 243
 - database
 - backup, 173
 - defining group and account on remote machine, 226
 - port number, 184
 - restore, 177
 - defaults
 - installation directories, 51
 - ports, 183-184
 - deployment
 - determining agent resources needed, 239-245
 - determining console resources needed, 252
 - determining hardware resources needed, 239
 - determining server resources needed, 245-252
 - Sun Fire platform agents, dedicated host, 254-255
 - Sun Fire platform agents, server layer host, 255
 - developer environment, 15
 - overview, 50-51
 - directories
 - Microsoft Windows, 51

- directories (Continued)
 - Solaris, 51
- directory size monitoring, system impact, 243
- disabling SNMP daemon, 159-160
- disk space requirements
 - Advanced System Monitoring add-on, 28
 - agent, 25, 26
 - Linux
 - Java console, 26
 - Microsoft Windows
 - Java console, 26
 - Performance Reporting Manager add-on, 28
 - server, 25
 - Service Availability Manager add-on, 28
 - Solaris Container Manager add-on, 28
 - Solaris platform
 - Java console, 26
 - System Reliability Manager add-on, 28
- documentation resources, 43-45
- domain administrators, definition of, 65
- domain-config.x file, 180
- domains, management approach, 69-70
- dynamic reconfiguration module, 242-243

E

- enterprise management platforms, integration
 - with, 199
- environment
 - development, 15
 - organizing, 70
 - production, 15
- environment variables
 - Linux, 79
 - Microsoft Windows 2000, 78-79
 - Microsoft Windows 98, 77-78
 - Microsoft Windows NT, 78-79
 - setting, 77-79
 - setting Windows 98 environment space, 81
 - setting Windows 98 swap space, 80
 - Solaris, 77
- es-backup, database and configuration
 - backup, 173
- es-config
 - options, 185-186
 - port number, reconfiguring, 185
 - restricting firewall port range, 196

- es-config (Continued)
 - RMI port address, reconfiguring, 185-186
- es-guisetup
 - running after installation, 33-40
 - setting up a single add-on, 33-40
 - setting up a single add-on with, 161-162
- es-inst, installing on a local
 - machine, 218-224
- es-inst
 - installing on a remote machine, 224-229
 - options, 217-218
- es-makeagent, creating base agent image for
 - JumpStart, 132
- es-restore, database and configuration
 - recovery, 177
- es-setup, options, 229-230
- es-setup, setting up a single add-on, 162
- es-start, options, 167
- es-stop, options, 171
- es-validate, options, 163-164
- esadm security group, 158
- esdomadm security group, 158
- esmaster, 178, 179
- esmultiip
 - agent configuration, 151-152
 - options, 148-149
 - server
 - adding an IP interface, 149-150
 - removing an IP interface, 150
- esops, security group, 158
- espublic, 178, 179
- event manager, port number, 184

F

- file monitoring, system impact, 244
- file scanning, system impact, 244
- file systems, Sun Management Center Solaris
 - directories, 51
- finish script, JumpStart, creating, 141-144
- firewall, port numbers, restricting, 196

G

- general users, definition of, 66
- groups, security for, 158

H

- handsfree installation of agents, 122
- hardware
 - determining resources needed, 239
 - documentation, 43-45
 - module availability, 242-243
 - recommended server configurations, 245
 - Sun StorEdge constraints, 81
 - T3 device preparation, 82
- health monitoring, system impact, 244
- heap size, 168
- host alias, network address translation, 260
- HP Jet Direct, system impact, 244
- HP OpenView Operations, integrating with Sun Management Center, 199-200

I

- install clients, adding to JumpStart, 146-148
- install response file
 - JumpStart, creating, 133-140
 - JumpStart, customizing, 138
- install server, JumpStart, creating, 131-132
- installation, 22-25
 - agents, 122
 - cd-image based, 85-87
 - creating installation CD images, 85-87
 - installing on a remote machine, 224-229
 - on Microsoft Windows, 153-155
 - on Solaris and on Linux, 29-32
 - preinstall information, 22-25
 - preparation checklist, 74
 - preparation tasks, 74
 - remote machine, defining database access, 226
 - selecting method, 85-89
 - using the command-line interface, 217-229
 - using the graphical wizard, 29-32
 - Web-based, 87-89
- integration with other enterprise management platforms, 199
 - BMC Patrol, 201
 - Computer Associates Unicenter TNG, 201-203
 - HP OpenView Operations, 199-200
 - Tivoli TME, 203-204
- IP addressing, 258

- IP addressing mode, 24
- IP interface
 - agent, configuring on a multi-IP machine, 151-152
 - server
 - adding an IP interface, 149-150
 - removing an IP interface, 150
- IPV6 instrumentation module, system impact, 244

J

- Java console
 - Linux
 - disk space requirements, 26
 - RAM requirements, 26
 - swap space requirements, 26
 - Microsoft Windows
 - disk space requirements, 26
 - RAM requirements, 26
 - swap space requirements, 26
 - overview, 48
 - requirements
 - Linux, 26
 - Microsoft Windows, 26
 - Solaris operating environment, 26
 - Solaris platform
 - disk space requirements, 26
 - RAM requirements, 26
 - swap space requirements, 26
- JAVA_HOME, setting, 77-79
- JDK software, 27
- JumpStart
 - add install client, 146-148
 - boot server, 127
 - concepts, 126
 - create base agent image, 132-133
 - create finish script, 141-144
 - create install server, 131-132
 - create JumpStart profiles, 140-141
 - create profile directory, 131-132
 - create rules file, 144-145
 - generate Sun Management Center install response file, 133-140
 - generate Sun Management Center setup response file, 136
 - install clients, 127

JumpStart (Continued)

- install server, 127
- process overview, 128-129
- profile server, 127
- required services, 128
- security considerations, 129-130
- task summary, 130
- validating files, 145-146

K

- kernel reader, system impact, 244
- keys, *See* security keys

L

- large enterprises, management approach, 72
- legacy agent, 181
- Linux
 - environment variables, 79
 - Java console
 - swap space requirements, 26
- list of Sun Management Center packages, 273
- list of Sun Management Center rpms, 273
- local zone
 - creating, 40-41
 - monitoring, 42
 - using an existing, 41-42
- logging into console, automatic, 167

M

- management approach
 - domains, 69-70
 - large enterprises, 72
 - organizing the Sun Management Center environment, 70-72
 - server context, 69
- management strategies, overview, 69-72
- message authentication, security, 68
- MIB-II, 244
- MIB-II simple, system impact, 244
- Microsoft Windows
 - installing Sun Management Center, 153-155

Microsoft Windows (Continued)

- Java console
 - swap space requirements, 26
 - PATH statement, 77-78
 - Sun Management Center directories, 51
 - uninstalling Sun Management Center, 211
 - Windows 2000 environment variables, 78-79
 - Windows 98 environment variables, 77-78
 - Windows NT environment variables, 78-79
- Microsoft Windows 98
 - setting minimum environment space, 81
 - setting minimum swap space, 80
- modules
 - config-reader, 242-243
 - dynamic reconfiguration, 242-243
 - hardware specific, 242-243
 - resource requirements, 243-245
 - system impact, 243
- monitoring a local zone, 42
- multi-home, *See* esmultiip
- multi-IP machine
 - adding an IP interface, 149-150
 - removing an IP interface, 150

N

- NAT, *See* network address translation
- netstat, determining port use, 184
- network address translation (NAT), 24, 258
 - complexity considerations, 259-260
 - concepts and definition, 257-259
 - configuration, 260
 - constraints, 261
 - enabling, 197-198
 - examples, 262
 - host maps, 260
 - hosts, 260
 - limitations, 261-262
 - logical identifiers, 261
 - requirements, 257
 - routing table, 261
- network addressing mode, 24
- NFS (network file system)
 - command-line installation, 224-229
 - file system impact, 244
 - sharing installation directory, 85-87
 - statistics system impact, 244

O

- online help, 31
- operating system requirements, 25
- operators, definition of, 66
- organizing, management approach, 70-72
- overview
 - base add-on products, 49
 - base components, 48
 - console, 48
 - developer environment, 50-51
 - firewall, 196
 - integration with other enterprise management platforms, 199
 - JumpStart task summary, 130
 - security, 65-69
 - server, 48
 - SNMP, 49
 - Sun Management Center, 47-64
 - Sun Management Center packages, 273
 - Sun Management Center rpms, 273
 - system files, 51-53
 - Web server, 49

P

- packages, Sun Management Center, 273
- passwords, 24
- patches
 - applying patch-only image, 122
 - creating patch-only update-image, 113
 - downloading, 114
 - required for remote machine install, 225-226
 - Sun StorEdge™ A5x00, 81
 - systems with more than 4 Gbytes, 76-77
- PATH statement
 - Linux, 79
 - Microsoft Windows 2000, 78-79
 - Microsoft Windows 98, 77-78
 - Microsoft Windows NT, 78-79
 - Solaris, 77
- Performance Reporting Manager, 49
 - configuration, 247-250
 - examples, 249
 - types, 248
 - disk space requirements, 28
 - operating system requirements, 28
 - supported architecture, 248

- permissions, 23
- platform agents, Sun Fire, 252-255
- port addresses, changing, 183-188
- ports, 183-184
 - Advanced System Monitoring, 184
 - agent, 184
 - changing, 183-188
 - configuration manager, 184
 - conflicts, 183-188
 - cstservice, 184
 - database, 184
 - default, 183-184
 - determining if in use, 184
 - event manager, 184
 - firewall, specifying range, 196
 - reconfiguring legacy SNMP agents, 181-183
 - reconfiguring SNMP, 185
 - remote method invocation, 185-186
 - restrictions, 260
 - secure Web server, 184
 - server, 184
 - topology manager, 184
 - trap handler, 184
 - Web server, 184
- preinstallation
 - information needed, 22-25
 - procedures, 73-89
 - selecting installation method, 85-89
 - setting environment variables, 77-79
 - setting Windows 98 environment space, 81
 - setting Windows 98 swap space, 80
- print spooler, system impact, 244
- prior versions, compatibility, 73-74
- PRM, *See* Performance Reporting Manager
- process monitoring, 245
- production environment, 15
- profile directory, JumpStart, creating, 131-132
- profiles, JumpStart, creating, 140-141

R

- RAM
 - requirements, 25
 - systems with more than 4 Gbytes, 76-77
- reconfiguring port addresses, 183-188
- regenerating security keys, 179-180

- remote machine
 - defining database access, 226
 - definition of, 224-229
 - determine host machine type, 227
 - determine Solaris version of, 227
 - installing using the command-line interface, 224-229
 - required OS patches for, 225-226
- remote method invocation, 180
 - client to server, 68
 - ports, reconfiguring, 185-186
- restore, database and configuration data, 177
- RMI, *See* remote method invocation
- RMI port address, 185-186
- routing table, network address translation, 261
- rpms, Sun Management Center, 273
- rules file, JumpStart, creating, 144-145

S

SAM, *See* Service Availability Manager

security

- adding account `smcorau` on a remote machine, 226
- administrators, 66
- assigning a user to a security group, 158-159
- client to server, 68
- cross-server communications, 67
- defining `smcorag` on a remote machine, 226
- domain administrators, 65
- `esadm` group, 158
- `esdomadm` group, 158
- `esops` group, 158
- general users, 66
- groups, 158
- JumpStart, 129-130
- message authentication, 68
- operators, 66
- overview, 65-69
- predefined user account, `smcorau`, 53
- server to agent, 67
- users, groups, and roles, 65-67
- security keys, 24, 178
 - considerations, 68-69
 - regenerating, 179-180
 - seed, 178
 - SNMP community string, 24

security keys (Continued)

- Web server, 24
- security seed, inputting automatically, 122
- seed-file*, 122
- selecting installation method, 85-89
- server
 - context, 69
 - determining resources needed, 245-252
 - disk space requirements, 25
 - domains, 69-70
 - impact of console users, 251-252
 - multi-IP machine
 - adding an IP interface, 149-150
 - removing an IP interface, 150
 - operating system requirements, 25
 - performance impacts, 250
 - port number, default, 184
 - port number, reconfiguring, 185-186
 - RAM requirements, 25
 - recommended hardware configurations, 245
 - security, 67
 - sizing, 246-247
 - specifying heap size, 168
 - swap space requirements, 25
- `server-config.x` file, 180
- Service Availability Manager, 49
 - disk space requirements, 28
 - operating system requirements, 28
- setting
 - Linux environment variables, 79
 - Microsoft Windows 2000 environment variables, 78-79
 - Microsoft Windows 98 environment space, 81
 - Microsoft Windows 98 environment variables, 77-78
 - Microsoft Windows 98 swap space, 80
 - Microsoft Windows NT environment variables, 78-79
 - Solaris environment variables, 77
- setting up Sun Management Center, 33-40
- `setup_install_server`, JumpStart, 131
- setup response file
 - JumpStart, creating, 136
 - JumpStart, customizing, 139
- sizing
 - determining agent resources needed, 239-245

- sizing (Continued)
 - determining console resources needed, 252
 - determining hardware resources needed, 239
 - determining server resources needed, 245-252
 - events per day and objects managed, 246
- smcorag, defining on a remote machine, 226
- smcorau
 - adding account on a remote machine, 226
 - predefined Sun Management Center accounts, 53
- SNMP, 49
 - community string, 24
 - community string considerations, 68-69
 - compatibility, 73
 - configuring subagents, 181-183
 - disabling, 159-160
 - legacy agents, 180-183
 - overview, 49
 - port definitions, 180
 - reconfiguring ports, 185
 - snmpdx agent, 159
 - stopping, 159-160
 - subagents, 181
- snmpdx agent, 159
- software, system requirements, 25-26
- Solaris Container Manager
 - disk space requirements, 28
 - operating system requirements, 28
- Solaris platform
 - Java console
 - swap space requirements, 26
 - process monitoring, system impact, 245
 - setting environment variables, 77
- Solstice Enterprise Agents, compatibility, 73
- Solstice SyMON 1.x software
 - coexisting with Sun Management Center, 92
 - compatibility, 73
- Solstice SyMON 1.x software, upgrading, 92
- starting
 - console on Microsoft Windows, 169
 - console on Solaris, 168-169
 - multiple Sun Fire platform agents, 254-255
 - Sun Management Center components Using
 - es-guistart, graphical user interface start, 166
- starting (Continued)
 - Sun Management Center components Using
 - es-start, 167
- stopping
 - components using es-stop, 170-171
 - SNMP daemon, 159-160
 - Sun Management Center components, 170
- storage devices
 - Sun StorEdge A5x00, 81
 - T3 preparation, 82
- subagent, 181
- Sun Enterprise SyMON, compatibility, 74
- Sun Enterprise SyMON 2.x, upgrading, 92
- Sun Fire platform agent
 - requirements, 253-254
 - starting, 254-255
- Sun Fire systems
 - architecture, 253
 - dedicated host platform agent
 - capacity, 254-255
 - deploying agents on a dedicated host, 254-255
 - deploying agents on a server layer host, 255
 - platform agents, 252-255
 - proxy, 252-255
 - server layer host platform agent
 - capacity, 255
- Sun Management Center, 47-64
 - coexisting with Solstice SyMON 1.x, 92
 - command-line setup, 229-238
 - compatibility with prior versions, 73-74
 - directories, 51
 - documentation resources, 43-45
 - graphical wizard setup, 33-40
 - installing on Microsoft Windows, 153-155
 - installing on the Solaris and Linux platform
 - using the graphical wizard, 29-32
 - installing using the command-line interface, 217-229
 - integration with other enterprise management platforms, 199
 - organizing the environment, 70
 - overview, 47-64
 - packages list, 273
 - rpms list, 273
 - system requirements, 73-74
 - uninstalling 2.x and 3.x using
 - es-guiuninst, 209-210

- Sun Management Center (Continued)
 - uninstalling 2.x and 3.x using `es-uninst`, 215
 - uninstalling Sun Management Center from Microsoft Windows, 211
- Sun Management Center 2.x
 - upgrading, 93
- Sun Management Center 3.0
 - upgrading the server, 95, 98
- Sun Management Center environment
 - organization
 - applications, 71-72
 - environmental, 71
 - physical, 70-71
 - services, 72
- Sun StorEdge
 - A5x00, system impact, 245
 - A5x00 patches, 81
 - T3 array, system impact, 245
- Sun VTS, compatibility, 73
- swap space requirements
 - Java console
 - Linux, 26
 - Microsoft Windows, 26
 - Solaris platform, 26
 - server, 25
- SysRM, *See* System Reliability Manager
- system files
 - `/etc/group`, 52
 - `/etc/passwd`, 53
 - `/etc/system`, 52
 - overview, 51-53
 - `/var/opt/SUNWsymon/cfg/esusers`, 53, 157
- system impact, `config-reader`, 243
- system logs, performance impact, 244
- System Reliability Manager, 49
 - disk space requirements, 28
 - operating system requirements, 28
- system requirements, 73-74
 - Advanced System Monitoring, 28
 - base add-ons, 28-29
 - base layers, 25-26
 - Java console,
 - Linux platform, 26
 - Solaris platform, 26
 - Windows platform, 26
 - management modules, 243-245

- system requirements (Continued)
 - network address translation, 257
 - Performance Reporting Manager, 28
 - Service Availability Manager, 28
 - Solaris, base add-ons, 28-29
 - Solaris, base layers, 25-26
 - Solaris Container Manager, 28
 - Sun Fire platform agent, 253-254
 - System Reliability Manager, 28

T

- T3 storage device, preparation, 82
- Tivoli TME, integrating with Sun Management Center, 203-204
- topology manager, port number, 184
- topology ports, firewall, 196
- trap handler, port number, 184

U

- uninstalling
 - Sun Management Center 2.x and 3.x using `es-guiuninst`, 209-210
 - Sun Management Center 2.x and 3.x using `es-uninst`, 215
 - Sun Management Center from Microsoft Windows, 211
 - using command-line interface, 215
 - using `es-guiuninst`, 209-210
 - using `es-uninst`, 215
 - using the graphical interface, 209-210
- update-image
 - add-on agent image, 103
 - base agent image, 103
 - base and add-on agent image, 103
 - base and add-on patches, 103
 - creating, 101
 - creating patch-only image, 113
 - creating using command-line tool, 109
 - creating using GUI tool, 103
 - installing agents, 122
 - patch-only, 113
- upgrading
 - considerations, 91
 - Solstice SyMON 1.x, 92

- upgrading (Continued)
 - Sun Enterprise SyMON 2.x, 92
 - Sun Management Center 2.x, 93
 - Sun Management Center 3.0 server, 95, 98
- user name, administrator, 24
- users
 - adding, 158
 - assigning a user to a security group, 158-159
 - overview, 157
- using an existing local zone, 41-42

V

- validating JumpStart files, 145-146
- validation tool, 162-164
- value too large for defined data type, 76-77
- virtual memory
 - agent, 242
 - settings, Microsoft Windows version 98, 80

W

- Web server, 49
 - default port number, 184
 - secure port number, 184
 - security key, 24
- Windows, *See* Microsoft Windows

X

- x86 agents, 240