



GNOME 2.2 Desktop on Linux User Guide

Sun Microsystems, Inc.
4150 Network Circle
Santa Clara, CA 95054
U.S.A.

Part No: 817-5309-10
April 2004

Copyright 2004 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. All rights reserved.

This product or document is protected by copyright and distributed under licenses restricting its use, copying, distribution, and decompilation. No part of this product or document may be reproduced in any form by any means without prior written authorization of Sun and its licensors, if any. Third-party software, including font technology, is copyrighted and licensed from Sun suppliers.

Parts of the product may be derived from Berkeley BSD systems, licensed from the University of California. UNIX is a registered trademark in the U.S. and other countries, exclusively licensed through X/Open Company, Ltd.

Sun, Sun Microsystems, the Sun logo, docs.sun.com, AnswerBook, AnswerBook2, and Solaris are trademarks, registered trademarks, or service marks of Sun Microsystems, Inc. in the U.S. and other countries. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. in the U.S. and other countries. Products bearing SPARC trademarks are based upon an architecture developed by Sun Microsystems, Inc.

The OPEN LOOK and Sun™ Graphical User Interface was developed by Sun Microsystems, Inc. for its users and licensees. Sun acknowledges the pioneering efforts of Xerox in researching and developing the concept of visual or graphical user interfaces for the computer industry. Sun holds a non-exclusive license from Xerox to the Xerox Graphical User Interface, which license also covers Sun's licensees who implement OPEN LOOK GUIs and otherwise comply with Sun's written license agreements.

U.S. Government Rights – Commercial software. Government users are subject to the Sun Microsystems, Inc. standard license agreement and applicable provisions of the FAR and its supplements.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

Copyright 2004 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. Tous droits réservés.

Ce produit ou document est protégé par un copyright et distribué avec des licences qui en restreignent l'utilisation, la copie, la distribution, et la décompilation. Aucune partie de ce produit ou document ne peut être reproduite sous aucune forme, par quelque moyen que ce soit, sans l'autorisation préalable et écrite de Sun et de ses bailleurs de licence, s'il y en a. Le logiciel détenu par des tiers, et qui comprend la technologie relative aux polices de caractères, est protégé par un copyright et licencié par des fournisseurs de Sun.

Des parties de ce produit pourront être dérivées du système Berkeley BSD licenciés par l'Université de Californie. UNIX est une marque déposée aux Etats-Unis et dans d'autres pays et licenciée exclusivement par X/Open Company, Ltd.

Sun, Sun Microsystems, le logo Sun, docs.sun.com, AnswerBook, AnswerBook2, et Solaris sont des marques de fabrique ou des marques déposées, ou marques de service, de Sun Microsystems, Inc. aux Etats-Unis et dans d'autres pays. Toutes les marques SPARC sont utilisées sous licence et sont des marques de fabrique ou des marques déposées de SPARC International, Inc. aux États-Unis et dans d'autres pays. Les produits portant les marques SPARC sont basés sur une architecture développée par Sun Microsystems, Inc.

L'interface d'utilisation graphique OPEN LOOK et Sun™ a été développée par Sun Microsystems, Inc. pour ses utilisateurs et licenciés. Sun reconnaît les efforts de pionniers de Xerox pour la recherche et le développement du concept des interfaces d'utilisation visuelle ou graphique pour l'industrie de l'informatique. Sun détient une licence non exclusive de Xerox sur l'interface d'utilisation graphique Xerox, cette licence couvrant également les licenciés de Sun qui mettent en place l'interface d'utilisation graphique OPEN LOOK et qui en outre se conforment aux licences écrites de Sun.

CETTE PUBLICATION EST FOURNIE "EN L'ETAT" ET AUCUNE GARANTIE, EXPRESSE OU IMPLICITE, N'EST ACCORDEE, Y COMPRIS DES GARANTIES CONCERNANT LA VALEUR MARCHANDE, L'APTITUDE DE LA PUBLICATION A REpondre A UNE UTILISATION PARTICULIERE, OU LE FAIT QU'ELLE NE SOIT PAS CONTREFAISANTE DE PRODUIT DE TIERS. CE DENI DE GARANTIE NE S'APPLIQUERAIT PAS, DANS LA MESURE OU IL SERAIT TENU JURIDIQUEMENT NUL ET NON AVENU.



040127@7940



Contents

Preface 13

Part I A Tour of the GNOME Desktop 17

1 Basic Skills 19

Mouse Skills 19

 Mouse Button Conventions 19

 Mouse Actions 20

 Mouse Action Terminology 21

 Mouse Pointers 21

Keyboard Skills 23

 General Shortcut Keys 23

 Window Shortcut Keys 24

 Panel Shortcut Keys 25

 Application Shortcut Keys 25

 Access Keys 26

Using Windows 27

 To Resize Panes 27

 Using Tables 27

2 Overview of the GNOME Desktop 29

Introducing GNOME Desktop Components 29

Panels 31

 To Create Panels 31

 To Delete Panels 31

To Hide Panels	31
To Add Objects to Panels	31
To Manipulate Panel Objects	34
Menus	34
Windows	35
Types of Windows	35
To Manipulate Windows	35
To Give Focus to a Window	36
Workspaces	37
To Switch Between Workspaces	37
To Add Workspaces	38
Nautilus File Manager	38
To Open Files From the File Manager	39
To Move Files Between Folders	40
Desktop and Desktop Objects	40
To Open Desktop Objects	40
To Add Objects to the Desktop	40
GNOME Desktop Preferences	41
Applications	41
To Find Out More	42
To Find Out More About GNOME Desktop Topics	43
To Find Out More About Applets	43
To Find Out More About Applications	43
3 GNOME Desktop Sessions	45
Starting a Session	45
To Log in to a Session	46
To Log in to a Session in a Different Language	46
To Lock Your Screen	46
Managing the Session	47
Defining Session Behavior When You Log In and Log Out	47
To Use Startup Applications	48
To Browse Applications in the Current Session	48
To Save Session Settings	48
Ending a Session	49

4 Working With Panels	51
Introducing Panels	51
Managing Your Panels	52
To Add a New Panel	52
To Interact With a Panel	52
To Move a Panel	52
To Hide a Panel	52
To Modify Panel Properties	53
To Delete a Panel	55
Panel Objects	55
Interacting With Panel Objects	55
To Add an Object to a Panel	56
To Modify the Properties of an Object	56
To Move a Panel Object	57
To Lock a Panel Object	58
To Remove a Panel Object	58
Applets	58
To Add an Applet to a Panel	58
To Select an Applet	59
To Modify Preferences for an Applet	59
Launchers	59
To Add a Launcher to a Panel	60
To Modify the Properties of a Launcher	63
Buttons	63
Force Quit Button	64
Lock Button	64
Log Out Button	65
Run Button	65
Screenshot Button	65
Search Button	66
Minimise Windows Button	66
Notification Area Applet	67
Menus	67
Drawers	68
To Open and Close a Drawer	68
To Add a Drawer to a Panel	69
To Add an Object to a Drawer	69
To Modify Drawer Properties	69

5	Working With Menus	71
	Introduction to Menus	71
	Menu Features	72
	Menu Item Popup Menu	72
	Applications Menu	73
	Actions Menu	74
	Using the Run Application Dialog	74
	To Take a Screenshot	75
	Main Menu	76
	To Open the Main Menu	77
	To Add a Main Menu to a Panel	77
	Menu Bar	77
	To Add a Menu Bar to a Panel	77
	Customizing Your Menus	78
	To Add a Menu	78
	To Add a Launcher to a Menu	79
	To Add a Launcher to an Empty Menu	79
	To Copy a Launcher to a Menu	79
	To Edit the Properties of a Menu	80
	To Edit a Menu Item	80
	To Delete an Item from a Menu	80
6	Working With Windows	81
	Windows and Workspaces	81
	Window Manager Behavior	82
	Types of Window	82
	Window Frames	84
	Menus and Applets for Working With Windows and Workspaces	85
	Window Menu	85
	Window List Applet	87
	Workspace Switcher Applet	88
	Using the Top Edge Panel to Work With Windows	89
	Manipulating Windows	90
	To Give Focus to a Window	90
	To Minimize a Window	90
	To Maximize a Window	91
	To Restore a Window	91

	To Close a Window	91
	To Resize a Window	91
	To Move a Window	92
	To Roll Up a Window	92
	To Put a Window on All Workspaces	93
	To Move a Window to Another Workspace	93
	Manipulating Workspaces	93
	To Switch Between Workspaces	93
	To Add Workspaces	94
	To Name Workspaces	94
	To Delete Workspaces	94
7	Nautilus File Manager	95
	Introduction to Nautilus File Manager	95
	File Manager Windows	96
	View Pane	98
	Side Pane	99
	Icons and Emblems	99
	Navigating Your Computer	101
	To Display a Folder	101
	Using the Tree From the Side Pane	102
	Opening Files	103
	To Access FTP Sites	104
	To Access Network Places	105
	Accessing Special URI Locations	106
	Using Your Navigation History	107
	To Bookmark Your Favorite Locations	108
	Managing Your Files and Folders	109
	Drag-and-Drop in the File Manager	109
	To Select Files and Folders	110
	To Move a File or Folder	111
	To Copy a File or Folder	111
	To Duplicate a File or Folder	112
	To Create a Folder	112
	To Rename a File or Folder	112
	To Move a File or Folder to Trash	112
	To Delete a File or Folder	113

To Create a Symbolic Link to a File or Folder	113
To View the Properties of a File or Folder	114
To Change Permissions	114
Adding Notes to Files and Folders	115
Using Trash	116
Modifying the Appearance of Files and Folders	117
To Add an Emblem to a File or Folder	117
To Add a New Emblem	117
To Change the Icon for a File or Folder	117
To Change the Size of Items in a View	118
Using Views to Display Your Files and Folders	119
Assigning Actions to Files	123
To Modify Actions	123
Customizing the File Manager	125
Setting Your Preferences	125
Changing Backgrounds	129
To Show and Hide Window Components	130
Using Removable Media	130
To Mount Media	130
To Display Media Contents	131
To Display Media Properties	131
To Format a Floppy Diskette	131
To Eject Media	133
Writing CDs	133
Running Scripts From the File Manager	134
Mounting and Unmounting a File System	135
To Mount a File System	135
To Unmount a File System	136
Using NFS Shares	137
To Add an NFS Share	137
To Remove an NFS Share	139
8 Using Your Desktop	141
Introduction to the Desktop	141
Desktop Objects	142
To Select Objects on the Desktop	142
To Open an Object from the Desktop	143

To Add a Launcher to the Desktop	143
To Add a Symbolic Link to the Desktop	143
Adding a File or Folder to the Desktop	144
To Rename a Desktop Object	145
To Remove an Object from the Desktop	145
To Delete an Object from the Desktop	145
To View the Properties of a Desktop Object	145
To Change the Permissions of a Desktop Object	146
To Add an Emblem to a Desktop Object	146
To Add a Note to a Desktop Object	146
To Change the Icon for a Desktop Object	146
To Resize a Desktop Object Icon	147
Using Trash on the Desktop	147
To Display Trash	147
To Empty Trash	148
Using the Desktop Menu	148
Changing the Pattern or Color of the Desktop	149

Part II Customizing Your GNOME Desktop 151

9 Starting Preference Tools	153
Starting a Preference Tool	153
Where to Find Preference Tools	153
10 Using Preference Tools	157
Customizing the Desktop Background	158
Configuring a CD Database	159
Customizing CD Device Options	160
Configuring File Associations	161
To Add a File Type	162
To Add a Service	163
Setting File Management Preferences	164
Choosing Default Fonts	164
Previewing Fonts	165
Configuring Your Internet Connection	166
Configuring Keyboard Accessibility Options	167
Basic Preferences	167

Filter Preferences	169
Mouse Preferences	169
Configuring Keyboard Preferences	170
Keyboard Preferences	170
Sound Preferences	171
Configuring Keyboard Layout	171
Customizing Menus and Toolbars in Applications	172
Setting Mouse Preferences	172
Buttons Preferences	173
Pointer Preferences	173
Motion Preferences	174
Configuring Multimedia Keys	174
Customizing Your Panels	175
Changing Your Password	175
Choosing Your Preferred Applications	175
Web Browser Preferences	176
Text Editor Preferences	176
Terminal Preferences	177
Setting Screen Resolution Preferences	177
Setting Screensaver Preferences	178
Display Modes Preferences	178
Advanced Preferences	179
Configuring Sessions	181
Setting Session Preferences	181
Setting Session Properties	182
Configuring Startup Applications	183
Customizing Keyboard Shortcuts	184
Configuring Printers	185
Setting Session Sharing Preferences	185
Setting Sound Preferences	186
General Sound Preferences	186
Sound Event Preferences	187
Customizing Themes	188
To Create a Custom Theme	188
To Install a New Theme	189
To Install a New Theme Option	189
To Delete a Theme Option	190
Customizing Windows	190

Part III GNOME Desktop Applications 193

- 11 Starting Applications 195**
 - Starting an Application 195
 - Where to Find Applications 195

Glossary 199

Index 203

Preface

GNOME 2.2 Desktop on Linux User Guide describes how to use the GNOME 2.2 Desktop on Linux.

Who Should Use This Book

This book is for users who plan to use the GNOME 2.2 Desktop as the default desktop environment.

Before You Read This Book

Before you read this book, you should ensure that you have some familiarity with the following topics:

- Three-button mouse devices
- Graphical user interfaces
- Command line interfaces

How This Book Is Organized

This book is organized as follows:

- Part I introduces the core GNOME Desktop components. This part also provides information that helps you to start working with the GNOME Desktop.
- Part II describes how to configure the GNOME Desktop.
- Part III describes how to start the applications in the GNOME Desktop.
- Glossary is a list of terms used in this book, and definitions of the terms.

Related Documentation

The following manuals are related to this guide:

- *GNOME 2.2 Desktop Accessibility Guide*
- *GNOME 2.2 Desktop on Linux System Administration Guide*

Accessing Sun Documentation Online

The docs.sun.comSM Web site enables you to access Sun technical documentation online. You can browse the docs.sun.com archive or search for a specific book title or subject. The URL is <http://docs.sun.com>.

Ordering Sun Documentation

Sun Microsystems offers select product documentation in print. For a list of documents and how to order them, see “Buy printed documentation” at <http://docs.sun.com>.

Typographic Conventions

The following table describes the typographic changes used in this book.

TABLE P-1 Typographic Conventions

Typeface or Symbol	Meaning	Example
AaBbCc123	The names of commands, files, and directories; on-screen computer output	Edit your <code>.login</code> file. Use <code>ls -a</code> to list all files. <code>machine_name%</code> you have mail.
AaBbCc123	What you type, contrasted with on-screen computer output	<code>machine_name%</code> su Password:
<i>AaBbCc123</i>	Command-line placeholder: replace with a real name or value	To delete a file, type rm <i>filename</i> .
<i>AaBbCc123</i>	Book titles, new words, or terms, or words to be emphasized.	Read Chapter 6 in <i>User's Guide</i> . These are called <i>class</i> options. You must be <i>root</i> to do this.

Shell Prompts in Command Examples

The following table shows the default system prompt and superuser prompt for the C shell, Bourne shell, and Korn shell.

TABLE P-2 Shell Prompts

Shell	Prompt
C shell prompt	<code>machine_name%</code>
C shell superuser prompt	<code>machine_name#</code>
Bourne shell and Korn shell prompt	<code>\$</code>
Bourne shell and Korn shell superuser prompt	<code>#</code>

A Tour of the GNOME Desktop

This section introduces the core components in the GNOME Desktop. The GNOME Desktop is very configurable, therefore this section covers the main functional possibilities of the GNOME Desktop features. If you want to find out how to implement the various configuration possibilities that are mentioned in this section, see *Customizing Your GNOME Desktop*.

The chapters in this section are as follows:

- *Basic Skills*
Read this chapter to find out about mouse usage, shortcut keys, basic window skills, and basic dialog skills.
- *Overview of the GNOME Desktop*
Read this chapter for an introduction to the major components and functions of the GNOME Desktop. If you do not read anything else in this manual, read this chapter.
- *GNOME Desktop Sessions*
Read this chapter for information about how to start, manage, and end GNOME Desktop sessions.
- *Working With Panels*
Read this chapter to find out more about using panels. Panels are a key component of the GNOME Desktop. This chapter tells you how to use the different parts of your panels, and how to invoke the available functions of the GNOME Desktop using panels.
- *Working With Menus*
Read this chapter to find out more about using menus.
- *Working With Windows*
Read this chapter to find out more about using windows. This chapter describes basic windows functions such as moving and resizing. This chapter also describes the controls that you use with windows.

- *Nautilus File Manager*

Read this chapter to find out more about the Nautilus file manager. This chapter describes how to use the file manager to work with your file system. This chapter also describes how to customize the file manager.

- *Using Your Desktop*

Read this chapter to find out more about using the *desktop*. The desktop is the part of the GNOME Desktop where there are no interface graphical items, such as panels and windows. This chapter describes how to use the desktop to start applications, and open your files and folders. The chapter also describes how to use **Trash** from the desktop, how to use the Desktop menu, and how to customize the desktop.

Basic Skills

This chapter introduces you to the basic skills that you need to work with the GNOME Desktop.

- “Mouse Skills” on page 19
- “Keyboard Skills” on page 23
- “Using Windows” on page 27

Mouse Skills

Even if you are very familiar with mouse devices, you should still familiarize yourself with the button conventions and action terminology used in this manual. This section also describes the mouse pointers.

Mouse Button Conventions

All the instructions in this manual are for the following types of mouse devices:

- Devices that are configured for right-hand users.
- Three button devices. If you have a two-button mouse device, then you press the two buttons simultaneously to simulate the effect of a middle mouse button.

The mouse button conventions used in this manual are as follows:

Mouse Button	Definition
Left mouse button	The button on the left side of a mouse device configured for normal right-hand use.
Middle mouse button	The middle button of a mouse device configured for normal right-hand use.
Right mouse button	The button on the right side of a mouse device configured for normal right-hand use.

To reverse the handedness of your mouse device, start the Mouse preference tool, then select the options that you require. If you do reverse the handedness of your mouse device, then you must reverse the mouse button conventions used in this manual.

Mouse Actions

The following table describes the actions that you can perform with the mouse:

Mouse Button	Usage
Left mouse button	Use to perform the following actions: <ul style="list-style-type: none">■ Select text.■ Choose items.■ Drag items.
Middle mouse button	Use to perform the following actions: <ul style="list-style-type: none">■ Paste text.■ Move items.
Right mouse button	Opens a menu for the selected object, if a menu applies.

For example, if you want to copy text then perform the following steps:

1. Select the text with the left mouse button.
2. Move the mouse pointer to the location where you want to copy the text.
3. Click on the middle mouse button.

You can also right-click on the desktop to open the Desktop menu.










Mouse Action Terminology



The conventions used in this manual to describe actions that you take with the mouse are as follows:

Action	Definition
Click	Press and release the left mouse button, without moving the mouse.
Click-and-hold	Press and do not release the left mouse button.
Left-click	Same as <i>click</i> . Left-click clarifies the action when there might be confusion with <i>right-click</i> .
Middle-click	Press and release the middle mouse button, without moving the mouse.
Right-click	Press and release the right mouse button, without moving the mouse.
Double-click	Press and release the left mouse button twice in rapid succession without moving the mouse.
Drag	Click-and-hold a mouse button, then move an object. For example, you can drag a window or an icon. The left and middle mouse buttons can perform drag actions.
Drag-and-drop	Click-and-hold a mouse button, then move an object. For example, you can drag-and-drop a window or an icon. Release the mouse button to place the object in a new location.
Grab	Point to an item that you can move, and click-and-hold on the mouse button. For example, you can grab the titlebar of a window, then drag the window to a new location.

Mouse Pointers

As you use the mouse, the appearance of the mouse pointer can change. The appearance of the pointer can provide feedback about a particular operation, location, or state. The following table lists and describes some of the mouse pointers.

Pointer	Associated Action	Description
	Point to an item, choose a menu item	Normal pointer. The pointer that appears during normal use of the mouse.
	Drag-and-drop	Move pointer. Indicates that when you drop the object, the object is moved from the old location to the new location.
	Drag-and-drop	Copy pointer. Indicates that when you drop the object, a copy of the object is created where you drop the object.
	Drag-and-drop	Symbolic link pointer. Indicates that when you drop the object, a <i>symbolic link</i> to the object is created where you drop the object. A symbolic link is a special type of file that points to another file or folder.
	Drag-and-drop	Ask pointer. Indicates that when you drop the object, a menu opens. You can choose to move or copy the object, or to create a symbolic link to the object.
	Drag-and-drop	Not available pointer. Indicates that you cannot drop the object at the current location.
	Move panel object	Move panel object pointer. Indicates that you have selected a panel object to move.
	Resize window horizontally	Horizontal resize pointer. Indicates that you have selected a vertical window border to resize the window horizontally.
	Resize window vertically	Vertical resize pointer. Indicates that you have selected a horizontal window border to resize the window vertically.

Pointer	Associated Action	Description
	Resize window horizontally and vertically	Corner resize pointer. Indicates that you have selected a corner of a window border to resize the window horizontally and vertically.
	Resize window pane or resize table column	Window pane or table column resize pointer. Indicates that you have selected a column in a table to resize.

Keyboard Skills

For almost every task that you can perform with the mouse, you can use the keyboard to perform the same task. *Shortcut keys* are keys that provide you with a quick way to perform a task.

You can use shortcut keys to perform general GNOME Desktop tasks and to work with interface items such as panels and windows. You can also use shortcut keys in applications. To customize your shortcut keys, use the Shortcuts preference tool.

You can also modify the GNOME Desktop preferences to use keyboard accessibility features.

The following sections describe the shortcut keys that you can use.

General Shortcut Keys

General shortcut keys enable you to use the keyboard to perform general GNOME Desktop tasks. The following table lists some general shortcut keys:

Default Shortcut Keys	Function
Ctrl + Esc	Opens the Main Menu.
Super + R	Displays the Run Application dialog.
Print Screen	Takes a screenshot.
Alt + Print Screen	Takes a screenshot of the window that has focus.

Default Shortcut Keys	Function
Ctrl + Alt + right arrow	Switches to the workspace to the right of the current workspace.
Ctrl + Alt + left arrow	Switches to the workspace to the left of the current workspace.
Ctrl + Alt + up arrow	Switches to the workspace above the current workspace.
Ctrl + Alt + down arrow	Switches to the workspace below the current workspace.
Ctrl + Alt + d	Minimizes all windows, and gives focus to the desktop.
F1	Starts the online help browser, and displays appropriate online Help.

Window Shortcut Keys

Window shortcut keys enable you to use the keyboard to perform window tasks. The following table lists some window shortcut keys:

Default Shortcut Keys	Function
Alt + Tab	Switches between windows. When you use these shortcut keys, a list of windows that you can select is displayed. Release the keys to select a window.
Alt + Esc	Switches between windows in reverse order. Release the keys to select a window.
F10	Opens the first menu on the left side of the menubar.
Alt + spacebar	Opens the Window Menu .
Arrow keys	Moves the focus between items in a menu.
Return	Chooses a menu item.
Esc	Closes an open menu.
Ctrl + Alt + right arrow	Switches to the workspace to the right of the current workspace.
Ctrl + Alt + left arrow	Switches to the workspace to the left of the current workspace.
Ctrl + Alt + up arrow	Switches to the workspace above the current workspace.
Ctrl + Alt + down arrow	Switches to the workspace below the current workspace.
Ctrl + Alt + d	Minimizes all windows, and gives focus to the desktop.

Panel Shortcut Keys

Panel shortcut keys enable you to use the keyboard to perform panel tasks. The following table lists panel shortcut keys:

Default Shortcut Keys	Function
Ctrl + Alt + Tab	Switches the focus between the panels and the desktop. When you use these shortcut keys, a list of items that you can select is displayed. Release the keys to select an item.
Ctrl + Alt + Esc	Switches the focus between the panels and the desktop. Release the keys to select an item.
Ctrl + F10	Opens the popup menu for the selected panel.
Tab	Switches the focus between objects on a panel.
Return	Chooses the selected panel object or menu item.
Shift + F10	Opens the popup menu for the selected panel object.
Arrow keys	Moves the focus between items in a menu. Moves the focus between interface items in an applet also.
Esc	Closes an open menu.
F10	Opens the Applications menu from the Menu Bar, if the Menu Bar is in a panel.

Application Shortcut Keys

Application shortcut keys enable you to perform application tasks. You can use shortcut keys to perform application tasks more quickly than if you use a mouse. The following table lists some application shortcut keys:

Shortcut Keys	Command
Ctrl + N	New
Ctrl + X	Cut
Ctrl + C	Copy
Ctrl + V	Paste
Ctrl + Z	Undo
Ctrl + S	Save
Ctrl + Q	Quit

Access Keys

A *menubar* is a bar at the top of a window that contains the menus for the application. An *access key* is an underlined letter in a menubar, menu, or dialog that you can use to perform an action. On a menubar, the access key for each menu is underlined.

To open a menu, press Alt, then press the access key. In the menu, the access key for each menu item is underlined. To choose a menu item, press the access key for the menu item. The following table shows example access keys from the Text Editor application:

Access Keys	Function
Alt + F	Opens the File menu.
N	Chooses the New item on the File menu.

You can also use access keys to access elements in a dialog. In a dialog, one letter in most dialog elements is underlined. To access a particular dialog element, press Alt, then press the access key. The following table shows an example access key from the **Preferences** dialog in the Text Editor application:

Access Key	Function
Alt + U	Gives focus to the Use default theme font check box.

You can use also other keys to navigate within a window or dialog.

Key	Function
Tab	Moves the focus from element to element in a window or dialog.
Arrow keys	Use the arrow keys to perform the following actions: <ul style="list-style-type: none">■ In a menubar, move the focus from one menu to the next menu. In an open menu, move the focus from one menu item to the next menu item.■ Move the focus from one option to the next option to make your selection, for example, within a group of radio buttons in a dialog.■ Change the value that a spin box displays.

Using Windows

This section provides information on how to use windows.

To Resize Panes

Some windows contain more than one *pane*. A pane is a subdivision of a window. For example, the Nautilus file manager window contains a side pane and a view pane. A window that contains panes has a resize handle on the edge between the panes. To resize the pane, grab the resize handle, then drag the edge to the size you require.

Using Tables

Some windows contain information that is organized in a table. This section describes how to work with tables.

To change the width of a column, drag one of the vertical edges of the column.

In some tables, you can sort the information by a particular column. To sort information in a table, click on the heading on top of the column by which you want to sort the information. An up arrow is displayed in the column heading by which the table is sorted. The following figure shows the up arrow.



To reverse the sort order, click on the column heading again. The up arrow changes to a down arrow. The down arrow indicates that the information in the column is sorted in reverse order.

In some tables, you can select multiple items. The following table describes how to select items in tables.

Task	Action
Select an item	Click on the item.
Select a group of contiguous items	Press-and-hold Shift. Click on the first item in the group, then click on the last item in the group.

Task	Action
Select multiple items	Press-and-hold Ctrl. Click on the items that you want to select.

Overview of the GNOME Desktop

This chapter introduces you to the features and main components of the GNOME Desktop. Before you start to use the GNOME Desktop read this chapter to familiarize yourself with the various features, and how the main components work. The GNOME Desktop is very configurable, so this chapter describes the typical default configuration, covering the following topics.

- “Introducing GNOME Desktop Components” on page 29
- “Panels” on page 31
- “Menus” on page 34
- “Windows” on page 35
- “Workspaces” on page 37
- “Nautilus File Manager” on page 38
- “Desktop and Desktop Objects” on page 40
- “GNOME Desktop Preferences” on page 41
- “Applications” on page 41
- “To Find Out More” on page 42

Introducing GNOME Desktop Components

When you start a GNOME Desktop session for the first time, you should see a default startup screen, with panels, windows, and various icons.

The major components of the GNOME Desktop are as follows:

- Panels
Panels are areas in the GNOME Desktop from which you can access all of your system applications and menus. Panels are very configurable.
- Menus

You can access all GNOME Desktop functions through menus. You can use the Applications menu to access almost all of the standard applications, commands, and configuration options. You can access the Applications menu from the Main Menu and from the Menu Bar applet. You can add the Main Menu and the Menu Bar applet to your panels.

The Menu Bar applet contains an Actions menu. The Actions menu contains commands that perform various functions, for example Find Files and Log Out. The items in the Actions menu are at the top level of the Main Menu.

- Windows

You can display many windows at the same time. You can run different applications in each window. The window manager provides frames and buttons for windows. The window manager enables you to perform standard actions such as move, close, and resize windows.

- Workspaces

You can subdivide the GNOME Desktop into separate *workspaces*. A workspace is a discrete area in which you can work. You can specify the number of workspaces in the GNOME Desktop. You can switch to a different workspace, but you can only display one workspace at a time.

- Nautilus file manager

The Nautilus file manager provides an integrated access point to your files and applications. You can display the contents of your files within a file manager window, or open the files in the appropriate application from the file manager. You can use the file manager to manage your files and folders.

- Desktop

The desktop is behind all of the other components on the desktop. The desktop is an active component of the user interface. You can place objects on the desktop to quickly access your files and directories, or to start applications that you use often. You can also right-click on the desktop to open a menu.

- Preferences

The GNOME Desktop contains dedicated *preference tools*. Each tool controls a particular part of the behavior of the GNOME Desktop. To start a preference tool, choose Preferences from the Main Menu. Choose the item that you want to configure from the submenu.

The most powerful features of the GNOME Desktop are the high degree of configurability and the multiple ways that you can perform tasks.

The components of the GNOME Desktop are interoperable. Usually, you can perform the same action in several different ways. For example, you can start applications from panels, from menus, or from the desktop.

Your system administrator can make configuration changes to suit your needs, so that the GNOME Desktop that you use might not be exactly the same as described in this chapter. Nevertheless, this chapter provides a useful quick guide to how to work with the GNOME Desktop.

Panels

You can add or delete panels at any time. When you start a session for the first time, the GNOME Desktop contains at least one panel.

You can perform the following actions with panels:

- Create panels.
- Delete panels.
- Hide panels.
- Add objects to panels.
- Manipulate panel objects.

To Create Panels

To add a panel, right-click on a vacant space on any panel, then choose New Panel. The new panel is added to the GNOME Desktop. The new panel contains no objects. You can customize the new panel to suit your preferences. You can add objects to the panel to fit your own requirements. You can also change the background of the panel. You can create as many panels as you want.

To Delete Panels

To delete a panel, right-click on the panel then choose Delete This Panel.

To Hide Panels

Panels can have hide buttons at each end of the panel. You click on the hide buttons to hide or show the panel.

To Add Objects to Panels

A panel can hold several types of objects. The panel in Figure 2–1 contains each type of panel object.




FIGURE 2-1 A Panel With Various Panel Objects

You can add any of the following objects to all types of panels:

- **Applets**

Applets are small, interactive applications that reside within a panel, for example CD Player in Figure 2-1. Each applet has a simple user interface that you can operate with the mouse or keyboard. The following applets appear in your panels by default:

- **Clock:** Displays the time. You can also configure Clock to display the date.
- **Window List:** Displays a button for each window that is open. You can click on a window list button to minimize and restore windows. By default, Window List appears in the edge panel at the bottom of the screen.
- **Workspace Switcher:** Displays a visual representation of your workspaces. You can use Workspace Switcher to switch between workspaces. By default, Workspace Switcher appears in the edge panel at the bottom of the screen.

To add an applet to a panel, right-click on a vacant space on the panel, then choose Add to Panel. Choose the applet that you require from one of the following submenus:

- Accessories
- Amusements
- Internet
- Multimedia
- Utility

- **Launchers**

A *launcher* starts a particular application, executes a command, or opens a file. The calculator icon in Figure 2-1 is a launcher for the Calculator application. A launcher can reside in a panel or in a menu. Click on the launcher to perform the action that is associated with the launcher.

You can create your own launchers for applications. For example, you can create a launcher for a word processor application that you use frequently, and place the launcher in a panel for convenient access. To add a new launcher to a panel, right-click on a vacant space on the panel, then choose Add to Panel → Launcher.

Alternatively, to add a launcher from a menu, right-click on a vacant space on the panel, then choose Add to Panel → Launcher from menu. Choose the launcher to add from the submenus.

- Action buttons

You can add buttons to your panels to provide quick access to common actions. You can add the following buttons to your panels:

- Force Quit: Use this button to terminate applications that do not respond to your commands.
- Lock: Click on this button to lock your screen. The lock icon in Figure 2–1 is the Lock button.
- Log Out: Click on this button to end your session
- Run: Click on this button to open the **Run Application** dialog, from which you can run commands.
- Screenshot: Click on this button to take a screenshot of the screen.
- Search: Click on this button to start the Search Tool application, from which you can search for files.
- Show Desktop: Click on this button to minimize all windows and show the desktop.

To add a button to a panel, right-click on a vacant space on the panel, then choose Add to Panel → Actions. You can then choose the button you require.

- Menus

You can access all GNOME Desktop functions through menus. To open a menu from a panel, click on the icon that represents the menu. To open a menu from the Menu Bar, click on the text that represents the menu.

Menus that you add to your panels are represented by an icon with an arrow. The arrow indicates that the icon represents a menu. For example, see the menu icon in Figure 2–1.

You can add the Main Menu to any of your panels. To add the Main Menu to a panel, right-click on a vacant space on the panel, then choose Add to Panel → Main Menu.

You can also add the Menu Bar to any of your panels. To add the Menu Bar to a panel, right-click on a vacant space on the panel, then choose Add to Panel → Menu Bar.

- Drawers

Drawers are sliding extensions to a panel that you can open or close from a drawer icon, as shown in Figure 2–1. Drawers can help you to organize your work when you run a lot of applications simultaneously. You can place all the same functional elements in a drawer that you can put in any other type of panel.

To add a drawer to a panel, right-click on a vacant space on the panel, then choose Add to Panel → Drawer.

To open a drawer click on the drawer. To close a drawer click on the drawer again.

To Manipulate Panel Objects

You can manipulate panel objects in the following ways:

- Move objects within a panel, or to another panel.
You can move any object to another location in the panel. You can also move an object from one panel to another panel. Use the middle mouse button to drag the panel object to the new location.
- Copy menu items to a panel.
Drag the item from the menu to the panel. Alternatively, if the menu item is a launcher right-click on the menu item, then choose Add this launcher to panel.

Menus

You can access all GNOME Desktop functions through menus. You can access your menus from the following GNOME Desktop components:

- Main Menu
The Main Menu contains the Applications menu, and various other functions. You can use the Applications menu to access almost all of the standard applications, commands, and configuration options.
To add a Main Menu to a panel, right-click on the panel then choose Add to Panel → Main Menu. Click on the Main Menu button on a panel to open the Main Menu.
- Menu Bar
Menu Bar contains Applications and Actions menus. You can use the Applications menu and the Actions menu to access almost all of the standard applications, commands, and configuration options.
To add Menu Bar to a panel, right-click on the panel then choose Add to Panel → Menu Bar.
- Panels
You can add as many additional menus as you want to any of your panels. To open a menu that you add to a panel, click on the menu icon on the panel. You can perform other actions on your menus, such as copy menu items to panels.

Windows

You can display many windows at the same time in the GNOME Desktop. Each window has a frame. The window frame contains active control elements that you can use to work with the window.

Types of Windows

The GNOME Desktop features the following types of window:

- Application windows

When you run an application, a frame usually borders the window. The top edge of the application window contains a titlebar. The titlebar contains buttons that you can use to work with the window. The buttons in an application window frame enable you to perform actions such as open the Window Menu, or close the window. The Window Menu provides commands that you can perform on the window.

- Dialog windows

Dialog windows are associated with interactive processes. A dialog window consists of the window frame, and a single interactive pane that provides information and controls for the user. This manual refers to the interactive part of a dialog window as a dialog. The frame of a dialog window contains buttons that enable you to open the Window Menu, or to close the dialog window.

To Manipulate Windows

You use the frame of an application window or dialog window to perform various actions with the window. Most of the control elements are located on the top edge of the window frame. Figure 2-2 shows the top edge of a frame for a typical application window.



FIGURE 2-2 Top Edge of Frame for a Typical Application Window

The active control elements of the window frame are as follows:

Control Element	Description
Window Menu button	Click on the Window Menu button to open the Window Menu.
Titlebar	You can use the titlebar to move and shade the window.
Minimize button	Click on the Minimize button to minimize the window.
Maximize button	You can use the Maximize button to maximize and restore the window. To maximize a window click on the Maximize button. To restore the window click on the Maximize button again.
Close Window button	Click on the Close Window button to close the window.
Border	Right-click on the border to open the Window Menu.

To change the size of windows grab the border of the window, but not the titlebar. Drag the border until the window is the size that you require.

To Give Focus to a Window

A window that has focus can receive input from the mouse and the keyboard. Only one window can have focus at a time. The window that has focus has a different appearance than other windows.

You can use the following elements to give focus to a window:

Element	Action
Mouse	Click on the window, if the window is visible.
Shortcut keys	Use shortcut keys to switch between the windows that are open. To give focus to a window, release the keys. The default shortcut keys to switch between windows are Alt + Tab.
Window List	Click on the button that represents the window in Window List.
Workspace Switcher	Click on the window that you want to give focus to in the Workspace Switcher display.

Workspaces

You can display many windows at the same time in your GNOME Desktop. Your windows are displayed in subdivisions of the GNOME Desktop that are called workspaces. A workspace is a discrete area in which you can work.

Every workspace contains the same desktop, the same panels, and the same menus. However, you can run different applications, and open different windows in each workspace. You can display only one workspace at a time in the GNOME Desktop but you can have windows open in other workspaces.

Workspaces enable you to organize the GNOME Desktop when you run many applications at the same time. When your current workspace becomes crowded with windows, you can move your work to another workspace. You can also switch to another workspace then start more applications.

Workspaces are displayed in the Workspace Switcher applet. In Figure 2–3, Workspace Switcher contains four workspaces. The first three workspaces contain open windows. The last workspace does not contain currently active windows.




FIGURE 2–3 Workspaces Displayed in Workspace Switcher

To Switch Between Workspaces

You can switch between workspaces in the following ways:

- In Workspace Switcher, click on the workspace where you want to work.

- Press Ctrl + Alt + right arrow to switch to the workspace on the right of the current workspace.
- Press Ctrl + Alt + left arrow to switch to the workspace on the left of the current workspace.

To Add Workspaces

To add workspaces to the GNOME Desktop, right-click on the Workspace Switcher applet, then choose Preferences. The **Workspace Switcher Preferences** dialog is displayed. Use the **Number of workspaces** spin box to specify the number of workspaces that you require.

Nautilus File Manager

The Nautilus file manager provides an integrated access point to your files, applications, FTP sites, and URIs. To open a file manager window, double-click on the **Documents** object on the desktop. The following figure shows a file manager window that displays the contents of a folder.



A file manager window can contain the following panes:

- | | |
|-----------|--|
| Side pane | Enables you to navigate through your files. This pane also displays information about the current file or folder. The side pane is on the left side of the window. |
| View pane | Displays the contents of files and folders. The view pane is on the right side of the window. |

The file manager enables you to do the following:

- View files and folders
You can view your files and folders as icons or as a list. You can view the contents of some types of file within a file manager window. Alternatively, you can open the files in the appropriate application from the file manager.
- Manage your files and folders
You can use the file manager to create, move, copy, rename, and remove files and folders.
- Run scripts
You can run scripts from the file manager, and you can select files and folders on which to run your scripts.
- Customize your files and folders
You can add emblems to your files and folders to indicate particular states. For example, you can add an **Important** emblem to a file to indicate that the file is important. You can also customize folders in the following ways:
 - Add a note to a folder.
 - Specify a custom background pattern for a folder.
 - Specify a zoom setting for a folder.
- Open special *Uniform Resource Identifiers* (URIs)
The GNOME Desktop contains special URIs that enable you to access particular functions from the file manager. For example, to access the preference tools, you can access the `preferences:///` URI in the file manager.
- Write CDs
The file manager provides a special location where you can copy files and folders that you want to write to a CD. You can write the contents of the location to a CD easily.

The file manager also creates the desktop.

To Open Files From the File Manager

To navigate to the folder where the file that you want to open resides, double-click on the folder icons in the view pane. When the file that you want to open is displayed, double-click on the file icon to open the file.

To Move Files Between Folders

You can move files between folders by opening two or more file manager windows. Open a different folder in each window, then drag the files from one window to the other.

Desktop and Desktop Objects

The desktop is an active component of the user interface. You can use the desktop to perform the following actions:

- Start your applications, and open your files and folders.
You can add *desktop objects* for convenient access to the files, folders, and applications that you use frequently. For example, you add a launcher for an application that you use often.
- Open the Desktop menu.
Right-click on the desktop to open the Desktop menu. You can use the Desktop menu to perform actions on the desktop.

The file manager manages the desktop.

To Open Desktop Objects

To open an object from the desktop, double-click on the object. You can set your preferences in a Nautilus window so that you click once on an object to execute the default action.

To Add Objects to the Desktop

You can add desktop objects for convenient access to files, folders, and applications that you use frequently. You can add objects to your desktop in the following ways:

- Use the Desktop menu to add a launcher to the desktop.
- Drag an object from a file manager window to the desktop. For example, you can create a symbolic link to a file that you use often, then drag the link to your desktop. The icon for the link is moved to the desktop. To open the file, double-click on the icon. You can also drag files and folders to the desktop.

- Drag an application launcher from a menu to the desktop. For example, you can open a menu that contains a launcher for an application that you use often, then drag the launcher to your desktop.

GNOME Desktop Preferences

You can use preference tools to configure almost every feature of the GNOME Desktop. Each tool controls a particular part of the behavior of the GNOME Desktop. For example, you can use a preference tool to select a theme for the GNOME Desktop. A *theme* is a group of coordinated settings that specify the visual appearance of a part of your interface.

You can start your preference tools in either of the following ways:

- Choose Preferences from the Main Menu, then choose the item that you require.
- Double-click on the **This Computer** object on the desktop. A Nautilus window opens at the **This Computer** location. Double-click on the **Preferences** object to display the preference tools. Double-click on the item that you require.

Applications

The applications that are provided with the GNOME Desktop share several characteristics. For example, the applications have a consistent look-and-feel. The applications share characteristics because the applications use the same programming libraries. An application that uses the standard GNOME programming libraries is called a *GNOME-compliant application*. For example, Nautilus and the gedit text editor are GNOME-compliant applications.

GNOME provides libraries in addition to the libraries provided by your operating system. The libraries enable GNOME to run your existing applications as well as GNOME-compliant applications. For example, if your operating system is UNIX-based, you can run your current X11 applications and Motif applications from the GNOME Desktop.

Some of the features of GNOME-compliant applications are as follows:

- Consistent look-and-feel

GNOME-compliant applications have a consistent look-and-feel. GNOME-compliant applications use the look-and-feel settings that you specify in the preference tools. You can use the following tools to change the look-and-feel of your GNOME-compliant applications:

- Menus & Toolbars preference tool
- Theme preference tool
- Menubars, toolbars, and statusbars

Most GNOME-compliant applications have a menubar, a toolbar, and a statusbar. The menubar always contains a File menu and a Help menu. The File menu always contains an Quit menu item, and the Help menu always contains an About menu item.

A *toolbar* is a bar that appears under the menubar. A toolbar contains buttons for the most commonly-used commands. A *statusbar* is a bar at the bottom of a window that provides information about the current state of what you are viewing in the window. GNOME-compliant applications might also contains other bars. For example, Nautilus contains a location bar.

Some of the bars in GNOME-compliant applications are detachable. That is, the bar has a handle that you can grab then drag the bar to another location. You can drag the bar to snap to another side of the window, or to another part of the screen. For example, you can detach the menubar, toolbar, and location bar in the file manager.

- Default shortcut keys

GNOME-compliant applications use the same shortcut keys to perform the same actions. For example, to quit a GNOME-compliant application, press Ctrl + Q. To undo an action in a GNOME-compliant application, press Ctrl + Z.

- Drag-and-drop

GNOME-compliant applications use the same protocol to implement drag-and-drop operations. Therefore, GNOME-compliant applications provide consistent feedback when you drag-and-drop items.

The use of the same protocol also enables GNOME-compliant applications to interoperate in a sophisticated manner. For example, GNOME-compliant applications recognize the format of the items that you drag. When you drag a HTML file from a Nautilus window to a web browser, the file is displayed in HTML format in the browser. However, when you drag the HTML file to a text editor, the file is displayed in plain text format in the text editor.

To Find Out More

The GNOME Desktop provides help if you want to find out more about the following areas:

- GNOME Desktop topics
- Applets
- Applications

To Find Out More About GNOME Desktop Topics

You can find out more about particular GNOME Desktop topics in the integrated help system. To start the help system, choose Help from the Main Menu.

To Find Out More About Applets

To find out more about a specific applet, right-click on the applet, then choose Help.

To Find Out More About Applications

To find out more about a specific application, start the application, then choose Help → Contents. Alternatively, start the application then press F1.

GNOME Desktop Sessions

This chapter provides the information you need to start, manage, and end a GNOME Desktop session.

- “Starting a Session” on page 45
- “To Lock Your Screen” on page 46
- “Managing the Session” on page 47
- “Ending a Session” on page 49

Starting a Session

A session occurs between the time that you log in to the GNOME Desktop and the time that you log out. The login screen is your gateway to the GNOME Desktop. The login screen provides fields for you to enter your username and password. The login screen enables you to select login options, for example you can select the language of your session.

You start a session when you log in. The session manager starts after your username and password are authenticated. The session manager enables you to manage the session. For example, you can save the state of your most recent session and return to that session the next time that you log in. The session manager saves and restores the following:

- The appearance and behavior settings, for example fonts, colors, and mouse settings.
- The applications that you were running, for example file manager and text editor windows. You cannot save and restore applications that the session manager does not manage. For example, if you start the vi editor from the command line in a terminal window, session manager cannot restore your editing session.

To Log in to a Session

To log in to a session, perform the following steps:

1. On the login screen, click on the **Session** icon. Choose the GNOME Desktop from the list of available desktop environments.
2. Enter your username in the **Username** field on the login screen, then press Return.
3. Enter your password in the **Password** field on the login screen, then press Return.

When you log in successfully, the session manager starts a session. If this is the first time you log in, then the session manager starts a new session. If you have logged in before, then the session manager restores your previous session, if you saved the settings for the previous session when you logged out.

If you want to shut down or restart the system before you log in, click on the **System** icon on the login screen. A dialog is displayed. Select the option that you require, then click OK.

To Log in to a Session in a Different Language

To log in to a session in a different language, perform the following actions.

1. On the login screen, click on the **Language** icon. Choose the language you require from the list of available languages.
2. Enter your username in the **Username** field on the login screen, then press Return.
3. Enter your password in the **Password** field on the login screen, then press Return.

Note – When you log in to a session in a different language, you choose the language for the user interface. You do not specify a keyboard layout for the session. To specify a keyboard layout, use the Keyboard Layout Switcher applet.

To Lock Your Screen



To lock the screen, perform one of the following actions:

- Choose Actions → Lock Screen.
- If the Lock button is present on a panel, click on the Lock button.
To add the Lock button to a panel, right-click on the panel. Choose Add to Panel → Actions → Lock.

When you lock your screen, the screensaver starts. To unlock the screen, move your mouse to display the locked screen dialog. Enter your username and password in the locked screen dialog, then press Return.

For information on configuring your screensaver, see *Using Preference Tools*.

Note – To lock your screen correctly, you must have a screensaver enabled.

Managing the Session

To configure the session management of the GNOME Desktop, use the Sessions preference tool. The Sessions preference tool recognizes the following types of application:

- Applications that are session-managed. When you save the settings for your session, the session manager saves all of the session-managed applications. If you log out, then log in again, the session manager automatically starts the session-managed applications.
- Applications that are not session-managed. When you save the settings for your session, the session manager does not save any applications that are not session-managed. If you log out, then log in again, the session manager does not start non-session-managed applications. You must start the application manually. Alternatively, you can use the Sessions preference tool to specify non-session-managed applications that you want to automatically start.

Defining Session Behavior When You Log In and Log Out

To set how a session behaves when you log in and log out, use Sessions preference tool. Make the changes you require in the **Session Options** tabbed section. For example, you can select to display a splash screen when you log in.

To Use Startup Applications

You can configure your sessions to start with applications that are not session-managed. To configure non-session-managed startup applications, use the Sessions preference tool. Use the **Startup Programs** tabbed section to add, edit, and delete applications. If you save your settings and log out, the next time that you log in, the startup applications start automatically.

To Browse Applications in the Current Session

To browse the applications in the current session, use the Sessions preference tool. The **Current Session** tabbed section lists the following:

- All GNOME applications that are currently running, that can connect to the session manager, and that can save the state of the application.
- All preference tools that can connect to the session manager, and that can save the state of the tool.

You can use the **Current Session** tabbed section to perform a limited number of actions on the session properties of an application or preference tool. For example, you can edit the startup order, and restart style of any GNOME application or preference tool that is in the list.

To Save Session Settings

To save your session settings, perform the following steps:

1. Configure your session to automatically save settings when you end the session. To configure your session, use the Sessions preference tool. The Sessions preference tool starts. Select the **Automatically save changes to session** option on the **Session Options** tabbed section.
2. End your session.

If you do not select the **Automatically save changes to session** option, when you log out, a dialog asks if you want to save your current settings. To save your settings, select the option, then continue to log out.

Ending a Session



To end your session, close all your currently active processes, then perform one of the following actions:

- Click on a Log Out button.
- Open the Main Menu, then choose Log Out *name*.

Before you end a session, you might want to save your current settings so that you can restore the session later. During the logout process, a dialog asks if you want to save your current settings. In the Sessions preference tool, you can select an option to automatically save your current settings.

Working With Panels

The information in this chapter describes how to use panels.

- “Introducing Panels” on page 51
- “Managing Your Panels” on page 52
- “Panel Objects” on page 55
- “Applets” on page 58
- “Launchers” on page 59
- “Buttons” on page 63
- “Menus” on page 67
- “Drawers” on page 68

Introducing Panels

A panel is an area in the GNOME Desktop from which you can run applications and applets, and perform other tasks. When you start a session for the first time, the GNOME Desktop contains at least one panel. Your system administrator might have set your default panels according to your local requirements, so you might see slightly different default panels.

You can change the behavior and appearance of your panels to suit your requirements. You can also add or remove objects from your panels. You can create multiple panels, and choose different properties, objects, and backgrounds for each panel. You can also hide panels.

Managing Your Panels

The following sections describe how to manage your panels.

To Add a New Panel

To add a panel, right-click on a vacant space on any panel, then choose New Panel. The new panel is added to the GNOME Desktop. The new panel contains no objects. You can customize the new panel to suit your preferences.

To Interact With a Panel

To interact with a panel, you must left-click, middle-click, or right-click on a vacant space on the panel. You can also middle-click or right-click on one of the hide buttons to select the panel, if the panel has no vacant space. If the hide buttons are not visible on a panel, modify the properties of the panel so that the hide buttons are visible.

You use the mouse buttons to interact with a panel in the following ways:

- Middle-click Enables you to grab a panel, then drag the panel to a new location.
- Right-click Opens the panel popup menu.


To Move a Panel

You can move panels to different locations. To move a panel, middle-click and hold on any vacant space on the panel, then drag the panel to the new location.

To Hide a Panel

You can hide or show panels. To hide a panel, use a hide button. If the hide buttons are not visible on a panel, modify the panel properties so that the hide buttons are visible.

Hide buttons are at either end of a panel. The hide buttons contain an optional arrow icon. The following illustration shows hide buttons.



To hide a panel, click on one of the hide buttons. The panel reduces in the direction of the arrow on the hide button. The hide button at the other end of the panel remains visible.

To show a hidden panel again, click on the visible hide button. The panel expands in the direction of the arrow on the hide button. Both hide buttons are now visible.

You can set a panel to autohide. When you set autohide, the panel hides automatically when the mouse is not pointing to the panel. The panel reappears when you point to the part of the screen where the panel resides. To set your panel to autohide, modify the properties of the panel.

To Modify Panel Properties

To modify preferences for all panels, use the **Panel** preference tool to make the changes that you require. For example, you can modify animation preferences for panels.

You can also modify properties for each individual panel. You can change the features for each panel, such as the position of the panel, the hide behavior, and the visual appearance.

To modify the properties of a panel, perform the following steps:

1. Right-click on a vacant space on the panel, then choose Properties to display the **Panel Properties** dialog. The **Panel Properties** dialog contains the following tabbed sections:
 - **General**
 - **Background**
2. To modify panel size, position, and hiding properties, click on the **General** tab. The following table describes the dialog elements on the **General** tabbed section:

Dialog Element	Description
Name	Type a name for the panel. When you use shortcut keys to switch between your panels and the desktop, this panel name is displayed.

Dialog Element	Description
Orientation	Select the position of the panel on your screen. Click on the required position for the panel.
Size	Use the spin box to specify the size of the panel.
Expand	Select this option if you want the panel to expand to the full length of the edge of the screen where the panel is located.
Autohide	Select this option to enable autohide.
Show hide buttons	Select this option to display hide buttons on your panel.
Arrows on hide button	Select this option to display arrows on the hide buttons, if the hide button is enabled.

3. To modify the panel background, click on the **Background** tab. Choose the type of background for the panel. The choices are as follows:

Dialog Element	Description
None (use system theme)	Select this option to use the default panel background. The default panel background depends on the settings in the Theme preference tool.
Solid color	Select this option to specify a single color for the panel background. Click on the Color button to display the color selector dialog. Choose the color that you require from the color selector dialog. Use the Style slider to specify the degree of transparency or opaqueness for the color. For example, to make the panel transparent, move the slider towards the Transparent end.
Background image	Select this option to specify an image for the panel background. Enter the filename of the image to use in the drop-down combination box. Alternatively, to browse for the file, click on the Browse button. When you have selected the file, click OK.

You can also drag a color or image on to a panel to set the color or image as the background of the panel. For more information, see “To Drag a Color or Image to the Background of a Panel” on page 55.

4. Click Close to close the **Panel Properties** dialog.

To Drag a Color or Image to the Background of a Panel

You can drag a color or image on to a panel to set the color or image as the background of the panel. You can drag a color or image from many applications. For example, you can drag a color from the Nautilus file manager to a panel to set the color as the background of the panel. You can also drag a color from any color selector dialog.

You can drag an image to a panel to set the image as the background of the panel. You can also drag pattern images from the file manager to set the background of the panel.

To Delete a Panel

To delete a panel from the GNOME Desktop, right-click on the panel that you want to delete, then choose Delete This Panel.

Note – You must always have at least one panel in the GNOME Desktop. If you have only one panel in the GNOME Desktop, you cannot delete that panel.

Panel Objects

This section describes the objects that you can add to your panels, and use from your panels.

Interacting With Panel Objects

You use the mouse buttons to interact with a panel object in the following ways:

- Left-click Launches the panel object.
- Middle-click Enables you to grab an object, then drag the object to a new location.
- Right-click Opens the panel object popup menu.

You interact with applet panel objects in a different way. For more information, see “To Select an Applet” on page 59.

To Add an Object to a Panel

You can add an object to a panel in several ways, as follows:

- From the panel popup menu
 - Right-click on a vacant space on a panel to open the panel popup menu. The panel popup menu contains an Add to Panel submenu. The Add to Panel submenu enables you to add the following objects to your panels:
 - Applets in the following categories: **Accessory, Amusement, Internet, Multimedia, Utility.**
 - Buttons for quick access to common actions: Force Quit button, Lock button, Log Out button, Minimise Windows button, Run button, Screenshot button, Search button .
 - Launchers
 - Launchers from menus
 - Main Menu
 - Menu Bar
 - Drawers
- From any menu
 - When you right-click on a launcher in any menu, a popup menu for the launcher opens. You can use this popup menu to add the launcher to a panel.
 - You can also drag menus, launchers, and applets from menus to panels.
- From the file manager
 - Each launcher corresponds to a `.desktop` file. You can drag the `.desktop` file on to your panels to add the launcher to the panel.

To Modify the Properties of an Object

Some panel objects, such as launchers and drawers, have a set of associated properties. The properties are different for each type of object. The properties specify details such as the following:

- The command that starts a launcher application.
- The location of the source files for a menu.
- The icon that represents the object.

To modify the properties of an object perform the following steps:

1. Right-click on the object to open the panel object popup menu, as shown in Figure 4-1.




FIGURE 4-1 Panel Object Popup Menu

2. Choose Properties. Use the **Properties** dialog to modify the properties as required. The properties in the **Properties** dialog depend on which object you select in step 1.
3. Click OK to apply the changes, then close the **Properties** dialog.

To Move a Panel Object

You can move panel objects within a panel, and from one panel to another panel. You can also move objects between panels and drawers.

To move a panel object, middle-click and hold on the object and drag the object to a new location. When you release the middle mouse button, the object anchors at the new location.

Alternatively, you can use the panel object popup menu to move an object, as follows:

1. Right-click on the object, then choose Move.
2. Point to the new location for the object, then click any mouse button to anchor the object to the new location. This location can be on any panel that is currently in the GNOME Desktop.

Movement of a panel object affects the position of other objects on the panel. To control how objects move on a panel, you can specify a movement mode. To specify the movement mode, press one of the following keys as you move the panel object:

Key	Movement Mode	Description
No key	Switched movement	The object swaps places with other panel objects. Switched movement is the default movement mode.
Alt key	Free movement	The object jumps over other panel objects into the next vacant space on the panel.
Shift key	Push movement	The object pushes other panel objects further along the panel.

To Lock a Panel Object

You can lock panel objects so that the objects stay in the same position on the panel. This feature is useful if you do not want some panel objects to change position when you move other panel objects.

To lock an object to the current location of the object in the panel, right-click on the object to open the panel object popup menu, then choose Lock. To unlock the object, right-click on the object, then choose Unlock.

To Remove a Panel Object

To remove an object from a panel right-click on the object to open the panel object popup menu, then choose Remove From Panel.

Applets

An applet is a small application whose user interface resides within a panel. You use the applet panel object to interact with the applet. For example, the following figure shows the following applets, from left to right:

- Window List: Displays the windows currently open on your system.
- CD Player: Enables you to control the compact disc player on your system.
- Volume Control: Enables you to control the volume of the speaker on your system.



To Add an Applet to a Panel

You can add an applet to a panel from the panel popup menu. Right-click on any vacant space on the panel to open the panel popup menu. Choose Add to Panel, then choose the applet that you want to add from one of the following submenus:

- Accessories
- Amusements
- Internet

- Multimedia
- Utility

Alternatively, drag the applet from the submenu on to the panel.

To Select an Applet

To modify the properties of an applet, you must first right-click on the applet to display the panel object popup menu. To move an applet, you must middle-click on the applet.

Some restrictions apply on where you can click on an applet in order to display the panel object popup menu, or to move the applet, as follows:

- Some applets have popup menus of applet-specific commands that open when you right-click on particular parts of the applet. For example, the Window List applet has a vertical handle on the left side, and buttons that represent your windows on the right side. To open the panel object popup menu for the Window List applet, you must right-click on the handle. If you right-click on a button on the right side, a popup menu for the button opens.
- Some applets have areas that you cannot use to select the applet. For example, the Command Line applet has a field in which you enter commands. You cannot middle-click or right-click on this field to select the applet. Instead, middle-click or right-click on another part of the applet.

To Modify Preferences for an Applet

To modify the preferences for an applet perform the following steps:

1. Right-click on the applet, then choose Preferences. Use the **Preferences** dialog to modify the preferences as required. The preferences for applets vary depending on the applet.
2. Click Close to close the **Preferences** dialog.

Launchers

When you click on a launcher, you initiate one of the following actions:

- Start a particular application.
- Execute a command.
- Open a folder in a file manager window.

- Open a browser at a particular *Uniform Resource Locator* (URL). A URL is the address of a particular location on the Web.
- Open special *Uniform Resource Identifiers* (URIs). The GNOME Desktop contains special URIs that enable you to access particular functions from the file manager.

You can find launchers in the following places in the GNOME Desktop:

- Panels: On panels, launchers are represented by icons.
- Menus: On menus, launchers are represented by menu items. The menu items usually have an icon beside the menu item.
- Desktop: On the desktop, launchers are represented by icons.

You can modify the properties of a launcher. For example, the properties of a launcher include the name of the launcher, the icon that represents the launcher, and how the launcher runs.

To Add a Launcher to a Panel

You can add a launcher to a panel in one of the following ways:

- From the panel popup menu
 - To create a new launcher, right-click on any vacant space on the panel, then choose Add to Panel → Launcher. A **Create Launcher** dialog is displayed. For more information on how to complete this dialog, see “To Create a Launcher With the Create Launcher Dialog” on page 60.
 - Alternatively, to add an existing launcher to the panel, choose Add to Panel → Launcher from menu from the panel popup menu. Choose the launcher that you want to add from the menu.
- From any menu
 - To add a launcher to a panel from any menu, perform one of the following steps:
 - Open a menu that contains the launcher. Drag the launcher on to the panel.
 - Open the menu that contains the launcher from the panel where you want the launcher to reside. Right-click on the title of the launcher. Choose Add this launcher to panel.
- From the file manager
 - To add a launcher to a panel from the file manager, find the `.desktop` file for the launcher in your file system. To add the launcher drag the `.desktop` file to the panel.

To Create a Launcher With the Create Launcher Dialog

To create a launcher with the **Create Launcher** dialog perform the following steps:

1. Right-click on any part of a panel to open the panel popup menu. Choose Add to Panel → Launcher to display the **Create Launcher** dialog. The dialog displays the **Basic** tabbed section.
2. Enter the properties of the launcher in the dialog. The following table describes the dialog elements on the **Basic** tabbed section:

Dialog Element	Description
Name	Use this text box to specify the name of the launcher. You can use the Advanced tab to add translations of the name. This name is the name that appears when you add the launcher to a menu or to the desktop.
Generic name	Use this text box to specify the class of application to which the launcher belongs. For example, you might type Text Editor in this text box for a gedit launcher. You can use the Advanced tab to add translations of the generic name.
Comment	Use this text box to specify a short description of the launcher. The comment is displayed as a tooltip when you point to the launcher icon on the panel. You can use the Advanced tabbed section to add translations of the comment.
Command	Use this field to specify a command to execute when you click on the launcher. For sample commands, see the next section.
Type	Use this drop-down combination box to specify the type of launcher. Select from the following: <ul style="list-style-type: none"> ■ Application: Select this option to create a launcher that starts an application. ■ Link: Select this option to create a launcher that links to a URI.
Icon	Choose an icon to represent the launcher. To choose an icon, click on the No Icon button. An icon selector dialog is displayed. Choose an icon from the dialog. Alternatively, to choose an icon from another directory, click Browse. When you choose an icon, click OK.
Run in Terminal	Select this option to run the application or command in a terminal window. Choose this option for an application or command that does not create a window in which to run.

3. To set advanced properties for the launcher, click on the **Advanced** tab. The **Launcher Properties** dialog displays the **Advanced** tabbed section.
4. Enter the advanced properties of the launcher in the dialog. The following table describes the dialog elements on the top part of the **Advanced** tabbed section:

Dialog Element	Description
Try this before using	Enter a command here to check before starting the launcher. If the command is executable and is in your path, the launcher appears on the panel.
Documentation	Enter the path to the help file for the launcher. If you enter a path in this field, a Help on <i>launcher-name</i> Application menu item is displayed on the popup menu for the launcher.

5. You can also add a translation of the **Name**, **Generic name**, and **Comment** fields from the **Basic** tabbed section. To add a translation, enter the details of the translation in the **Name/Comment translations** table as follows:

Field	Description
First field	Enter the two-letter code for the language for which you want to add a translation.
Second field	Enter the translation of the Name of the launcher.
Third field	Enter the translation of the Generic name of the launcher.
Fourth field	Enter the translation for the Comment for the launcher.

Then click on the Add/Set button.

To edit a translation, select the translation. The translated text appears in the lower part of this dialog. Edit the fields as required, then click on the Add/Set button.

To remove a translation, select the translation, then click on the Remove button.

6. To create the launcher and close the **Launcher Properties** dialog, click OK.

Launcher Commands

The type of commands that you can enter in the **Command** field depend on the option that you choose from the **Type** drop-down combination box. If you choose **Application** from the **Type** drop-down combination box, you can enter a normal command. The following table shows some sample commands and the actions that the commands perform:

Sample Application Command	Action
<code>gedit</code>	Starts the gedit text editor application.

Sample Application Command	Action
<code>gedit /user123/loremipsum.txt</code>	Opens the file <code>/user123/loremipsum.txt</code> in the gedit text editor application.
<code>nautilus /user123/Projects</code>	Opens the folder <code>/user123/Projects</code> in a file manager window.

If you choose **Link** from the **Type** drop-down combination box, you can enter a link command. The following table shows some sample link commands and the actions that the commands perform:

Sample Link Command	Action
<code>http://www.gnome.org</code>	Opens the GNOME website in your default browser.
<code>ftp://ftp.gnome.org</code>	Opens the GNOME FTP site in your default browser.
<code>applications:///</code>	Opens the Applications location in a file manager window. Double-click on an application to start the application.
<code>preferences:///</code>	Opens the Desktop Preferences location in a file manager window. Double-click on a preference tool to start the preference tool.

To Modify the Properties of a Launcher

To modify the properties of a launcher perform the following steps:

1. Right-click on the launcher to open the panel object popup menu.
2. Choose Properties. Use the **Launcher Properties** dialog to modify the properties as required. For more information on the **Launcher Properties** dialog, see “To Create a Launcher With the Create Launcher Dialog” on page 60.
3. Click Close to close the **Launcher Properties** dialog.

Buttons

You can add buttons to your panels to provide quick access to common actions and functions.

Force Quit Button



The Force Quit button enables you to select a window to terminate an application. This button is useful if you want to terminate an application that does not respond to your commands.

To terminate an application, click on the Force Quit button, then click on a window from the application that you want to terminate. If you do not want to terminate an application after you click on the Force Quit button, press Esc.

Lock Button



The Lock button locks your screen and activates your screensaver. To access your session again, you must enter your password. To lock your screen correctly, you must have a screensaver enabled.

To add a Lock button to a panel, right-click on any vacant space on the panel. Choose Add to Panel → Actions → Lock.

Right-click on the Lock button to open a menu of screensaver-related commands. Table 4–1 describes the commands that are available from the menu.

TABLE 4–1 Lock Screen Menu Items

Menu Item	Function
Activate Screensaver	Activates the screensaver immediately, but does not lock the screen.
Lock Screen	Locks the screen immediately. This command performs the same function as when you click on the Lock button.

TABLE 4-1 Lock Screen Menu Items (Continued)

Menu Item	Function
Kill Screensaver Daemon	Terminates the screensaver process. After you terminate the screensaver process, you cannot lock your screen.
Restart Screensaver Daemon	Terminates and restarts the screensaver process. Use this command after you change your password. When you restart the screensaver process, use your new password with the screensaver.
Properties	Displays the XScreenSaver preference tool.

Log Out Button



The Log Out button begins the process to log out of a GNOME session.

To add a Log Out button to a panel, right-click on any vacant space on the panel. Choose Add to Panel → Actions → Log Out. To log out of your session or shut down your system, click on the Log Out button.

Run Button



You can use the Run button to open the **Run Application** dialog.

To add a Run button to a panel, right-click on any vacant space on the panel. Choose Add to Panel → Actions → Run. To open the **Run Application** dialog, click on the Run button.

For more information on the **Run Application** dialog, see *Working With Menus*.

Screenshot Button



You can use the Screenshot button to take a screenshot of your screen.

To add a Screenshot button to a panel, right-click on any vacant space on the panel. Choose Add to Panel → Actions → Screenshot. To take a screenshot of your screen, click on the Screenshot button.

For more information on how to take screenshots, see *Working With Menus*.

Search Button



You can use the Search button to open the Search Tool.

To add a Search button to a panel, right-click on any vacant space on the panel. Choose Add to Panel → Actions → Search. To open the Search Tool, click on the Search button.

For more information on the Search Tool, see the *Search Tool Manual*.

Minimise Windows Button



You can use the Minimise Windows button to minimize all open windows and show the desktop.

To add a Minimise Windows button to a panel, right-click on any vacant space on the panel. Choose Add to Panel → Actions → Minimise Windows. To minimize all windows and show the desktop, click on the Minimise Windows button.

Notification Area Applet



The Notification Area applet displays icons from various applications to indicate activity in the application. For example, when you use the CD Player application to play a CD, a CD icon is displayed in the Notification Area applet. The graphic above illustrates the CD icon in the Notification Area applet.

To add a Notification Area applet to a panel, right-click on any vacant space on the panel. Choose Add to Panel → Utility → Notification Area.

Menus

You can add the following types of menu to your panels:

- **Main Menu:** You can access almost all of the standard applications, commands, and configuration options from the Main Menu. To add a Main Menu to a panel, right-click on any vacant space on the panel, then choose Add to Panel → Main Menu. You can add as many Main Menu objects to your panels as you want.
- **Menu Bar:** You can access almost all of the standard applications, commands, and configuration options from the menus in the Menu Bar. The Menu Bar contains the Applications menu and the Actions menu. To add a Menu Bar to a panel, right-click on any vacant space on the panel, then choose Add to Panel → Menu Bar. You can add as many Menu Bar objects to your panels as you want.
- **System menus:** System menus contain the standard applications and tools that you can use in the GNOME Desktop. The Applications menu and Actions menu are system menus. To add a system menu to a panel, right-click on a launcher in the menu, then choose Entire menu → Add this as menu to panel.

Menus that you add to your panels are represented by an icon with an arrow. The arrow indicates that the icon represents a menu or drawer. Figure 4–2 shows how menus typically appear on panels.



FIGURE 4-2 Typical Menu Objects on a Panel

Drawers

A drawer is an extension of a panel. You can open and close a drawer in the same way that you can show and hide a panel. A drawer can contain all panel objects, including launchers, menus, applets, other panel objects, and other drawers. When you open a drawer, you can use the objects in the same way that you use objects on a panel.

The following figure shows an open drawer that contains two panel objects.



The arrow on the drawer icon indicates that the icon represents a drawer or menu.

You can add, move, and remove objects from drawers in the same way that you add, move, and remove objects from panels.

To Open and Close a Drawer

To open a drawer, click on the drawer object in a panel. You can close a drawer in the following ways:

- Click on the drawer.
- Click on the drawer hide button.

To Add a Drawer to a Panel

You can add a drawer to a panel in the following ways:

- From the panel popup menu
Right-click on any vacant space on the panel, then choose Add to Panel → Drawer.
- From any menu
You can add a menu as a drawer object to a panel.
To add a menu as a drawer to a panel, open the menu from the panel. Right-click on any launcher in the menu, then choose Entire menu → Add this as drawer to panel.

To Add an Object to a Drawer

You add an object to a drawer in the same way that you add objects to panels. For more information, see “To Add an Object to a Panel” on page 56.

To Modify Drawer Properties

To modify preferences for all panels and drawers, use the Panel preference tool. For example, you can select various options related to the appearance and behavior of objects on panels and drawers. You can also select options that relate to drawers only. For example, you can select an option to close your drawers when you click on a launcher in the drawer.

You can also modify other properties for each individual drawer. You can change features for each drawer, such as the visual appearance of the drawer and whether the drawer has hide buttons.

To modify properties for a drawer perform the following steps:

1. Right-click on the drawer, then choose Properties to display the **Panel Properties** dialog. The dialog displays the **General** tabbed section.
2. Select the properties for the drawer in the dialog. The following table describes the elements on the **General** tabbed section:

Dialog Element	Description
Name	Type a name for the panel. When you use shortcut keys to switch between your panels and the desktop, this panel name is displayed.
Size	Select the size of the panel.

Dialog Element	Description
Icon	Choose an icon to represent the drawer. Click on the Icon button to display an icon selector dialog. Choose an icon from the dialog. Alternatively, click Browse to choose an icon from another directory. When you choose an icon, click OK.
Show hide buttons	Select this option to display hide buttons on your panel.
Arrows on hide button	Select this option to display arrows on the hide buttons, if the hide button is enabled.

3. You can use the **Background** tabbed section to set the background for the drawer. For information on how to complete the **Background** tabbed section, see the step on this topic in “To Modify Panel Properties” on page 53. You can also drag a color or image on to a drawer to set the color or image as the background of the drawer. For more information, see “To Drag a Color or Image to the Background of a Panel” on page 55.
4. Click Close to close the **Panel Properties** dialog.

Working With Menus

This chapter describes how to use menus in the GNOME Desktop.

- “Introduction to Menus” on page 71
- “Menu Features” on page 72
- “Applications Menu” on page 73
- “Actions Menu” on page 74
- “Main Menu” on page 76
- “Menu Bar” on page 77
- “Customizing Your Menus” on page 78

Introduction to Menus

You can access all GNOME Desktop functions through menus. The panels contains menus, so you can use a combination of menus and panels to perform your tasks. You can perform various actions on your menus, such as copy menu items to panels.

You can access the following menus in the GNOME Desktop:

- **Main Menu:** You can access the items in the Applications menu from the Main Menu. You can have many Main Menu buttons in your panels. You can also access the items in the Actions menu from the Main Menu. The items in the Actions menu are at the top level of the Main Menu.
- **Menu Bar:** You can access the items in the Applications and Actions menus from Menu Bar. You can have many Menu Bar applets in your panels.
- **Applications menu:** You can access many of your applications, commands, and configuration options from the Applications menu.
- **Actions menu:** You can access commands that enable you to perform various tasks from the Actions menu. For example, you can start the Search Tool application, or log out of the GNOME Desktop.

You can also right-click on the desktop to open the Desktop menu. The Desktop menu enables you to perform desktop-related tasks.

All of these menus provide you with multiple ways to perform your tasks, and enable you to work in the way that you prefer.

Menu Features

Menus can contain the following items:

- Submenus
- Launchers or menu items

An arrow to the right of an item in a menu indicates that the item is a submenu. When you point to the submenu, the submenu opens. You can choose items from the submenu.

When you choose a launcher, the launcher starts an application or runs a command. You can also right-click on a launcher to open a popup menu. The popup menu enables you to add the item to a panel, and perform other tasks. For more information on the popup menu, see the next section.

You can change the theme for your session to change how all your menus look. To change the theme, use the Theme preference tool.

Menu Item Popup Menu

Items in menus have an associated popup menu that enables you to perform tasks related to the item. When you right-click on an item in a menu, the popup menu for the item opens. The popup menu also contains a submenu that allows you to perform menu-related tasks.

You can use the menu item popup menu to perform the following tasks:

- Add menu items as launchers to panels.
- Remove items from menus.
- Open the **Run Application** dialog with the menu item command in the dialog.
- Add menus to panels. You can add a menu as a menu object or as a drawer object.
- Add new items to menus.
- Change the properties of submenus and menu items.

Figure 5-1 shows the popup menu.




FIGURE 5-1 Menu Item Popup Menu

Table 5-1 describes menu item popup menus.

TABLE 5-1 Menu Item Popup Menus

Item	Description
Add this launcher to panel	Adds the launcher to the panel from which you open the menu.
Remove this item	Removes the launcher from the menu.
Put into run dialog	Displays the Run Application dialog with the command from the Command field of the launcher in the command field on the Run Application dialog.
Help on <i>application-name</i>	Opens the online help for the application.
Properties	Displays a dialog that enables you to edit the properties of the launcher.
Entire menu → Add this as drawer to panel	Adds the submenu as a drawer to the panel from which you open the menu.
Entire menu → Add this as menu to panel	Adds the submenu as a menu object to the panel from which you open the menu.
Entire menu → Add new item to this menu	Enables you to add an item to the submenu.
Entire menu → Properties	Displays a dialog that enables you to edit the properties of the submenu.

Applications Menu

The Applications menu contains a hierarchy of submenus, from which you can start the standard GNOME applications and preference tools.

The Applications menu resides in the following places:

- Main Menu
- Menu Bar

Actions Menu

The Actions menu contains commands that enable you to perform various tasks in the GNOME Desktop. Table 5–2 describes the commands in the Actions menu.

TABLE 5–2 Actions Menu Commands

Menu Item	Function
Run Application	Opens the Run Application dialog. Use the Run Application dialog to run commands. For more information, see “Using the Run Application Dialog” on page 74.
Open Recent	Displays a submenu of the last ten files which you saved.
Find Files	Starts the Search Tool application. For more information, see the <i>Search Tool</i> manual.
Lock Screen	Locks your screen.
Log Out	Logs you out of the current session.

The Actions menu resides in the following places:

- Main Menu. The items in the Actions menu are at the top level of the Main Menu.
- Menu Bar.

Using the Run Application Dialog

The **Run Application** dialog gives you access to the command line. When you run a command in the **Run Application** dialog, you cannot receive output from the command.

To run a command from the command line perform the following steps:

1. Display the **Run Application** dialog. You can display the **Run Application** dialog in any of the following ways:
 - From any panel
Add the Run button to a panel. Right-click on the panel, then choose Add to Panel → Actions → Run. Click on the Run button.

- From the Main Menu
Open the Main Menu, then choose Run Application.
 - From the Menu Bar
Choose Actions → Run Application.
 - Use shortcut keys
The default shortcut keys to display the **Run Application** dialog are Super + R. You can change the shortcut keys that display the **Run Application** dialog in the Keyboard Shortcuts preference tool.
 - From a menu item popup menu
Right-click on an item in a menu, then choose **Put into run dialog** from the popup menu. The **Run Application** dialog opens with the command from the menu in the command field. The **Run Application** dialog is displayed.
2. Enter the command that you want to run in the blank field. Alternatively, to choose a command that you ran previously, click the down arrow button beside the command field, then choose the command to run.

Alternatively, select the Show list of known applications option to display a list of available applications.

You can also use the Run with file button to choose a file to append to the command line. For example, you can enter emacs as the command, then choose a file to edit.

Select the **Run in terminal** option to run the application or command in a terminal window. Choose this option for an application or command that does not create a window in which to run.
 3. Click on the Run button on the **Run Application** dialog.

To Take a Screenshot

You can take a screenshot in any of the following ways:

- From any panel
Add the Screenshot button to a panel. Right-click on the panel, then choose Add to Panel → Actions → Screenshot. Click on the Screenshot button to take a screenshot of the entire screen. Use the **Save Screenshot** dialog to save the screenshot.
- Use shortcut keys
To take a screenshot, use the following shortcut keys:

Default Shortcut Keys	Function
Print Screen	Takes a screenshot of the entire screen, and displays the Save Screenshot dialog. Use the Save Screenshot dialog to save the screenshot.

Default Shortcut Keys	Function
Alt + Print Screen	Takes a screenshot of the window to which the mouse points, and displays the Save Screenshot dialog. Use the Save Screenshot dialog to save the screenshot.

You can use the Keyboard Shortcuts preference tool to modify the default shortcut keys.

- From Menu Bar

To take a screenshot of the entire screen, choose Actions → Take Screenshot. A **Save Screenshot** dialog is displayed. To save the screenshot, select the **Save screenshot to file** option. Enter the path and filename for the screenshot in the drop-down combination box. Alternatively, to save the screenshot to another directory, click Browse. When you select a directory, click OK.

You can also save the screenshot to the desktop. To save the screenshot to the desktop, select the **Save screenshot to desktop** option.

- Use a command

You can use the `gnome-panel-screenshot` command to take a screenshot. The `gnome-panel-screenshot` command takes a screenshot of the entire screen, and displays the **Save Screenshot** dialog. Use the **Save Screenshot** dialog to save the screenshot.

You can also use options on the `gnome-panel-screenshot` command as follows:

Option	Function
<code>--window</code>	Takes a screenshot of the window that has focus, and displays the Save Screenshot dialog. Use the Save Screenshot dialog to save the screenshot.
<code>--delay=seconds</code>	Takes a screenshot after the specified number of seconds, and displays the Save Screenshot dialog. Use the Save Screenshot dialog to save the screenshot.
<code>--help</code>	Displays the options for the command.

Main Menu

The Main Menu provides access to the Applications menu and many of the items in the Actions menu. You can access almost all of the standard applications, commands, and configuration options from the Main Menu.

You can add Main Menu buttons to your panels.

To Open the Main Menu

You can open the Main Menu in the following ways:

- From a panel with a Main Menu

Click on the Main Menu.

- Use shortcut keys


You can use shortcut keys to open the Main Menu. When you use shortcut keys to open the Main Menu, the Main Menu appears at the mouse pointer.

The default shortcut keys to open the Main Menu are Ctrl + Esc. To change the shortcut keys that open the Main Menu, use the Keyboard Shortcuts preference tool.

To Add a Main Menu to a Panel

You can add as many Main Menu buttons as you want to your panels. To add a Main Menu to a panel, right-click on any vacant space on the panel. Choose Add to Panel → Main Menu.

Menu Bar



The Menu Bar provides access to the Applications and Actions menus. You can access almost all of the standard applications, commands, and configuration options from the Menu Bar.

To Add a Menu Bar to a Panel

You can add as many Menu Bar applets as you want to your panels. To add a Menu Bar to a panel, right-click on any vacant space on the panel. Choose Add to Panel → Menu Bar.

Customizing Your Menus

You can modify the contents of the following menus:

- Applications menu
- Preferences menu

You use the following GNOME Desktop components to customize menus:

- Menus on panels
- Nautilus file manager

When you use panels to customize your menus, you use the menu item popup menu. For more information, see “Menu Item Popup Menu” on page 72.

When you use the file manager to customize your menus, you must access the Applications menu or the Preferences menu from within the file manager. To access the Applications menu or the Preferences menu, open a file manager window.

To access menus in the file manager, enter one of the following URIs in the field on the location bar:

Menu	Enter this URI
Applications menu	<code>applications:///</code>
Preferences menu	<code>preferences:///</code>

For more information on the file manager, see *Nautilus File Manager*.

To Add a Menu

To add a menu, perform the following steps:

1. In a file manager window, access the location where you want to add the menu. For example, if you want to add a menu to the Applications menu, enter `applications:///` in the field on the location bar.
2. Choose File → New Folder. An untitled folder is added to the view pane. The name of the folder is selected.
3. Type a name for the folder, then press Return.

The next time that you log out then log in again, the menu is in the assigned location.

To Add a Launcher to a Menu

To add a launcher to a menu, perform the following steps:

1. Right-click on any item in the menu to which you want to add the launcher.
2. Choose Entire menu → Add new item to this menu. A **Create Launcher** dialog is displayed.
3. Enter the properties of the launcher in the **Create Launcher** dialog. For more information on the elements in the **Create Launcher** dialog, see *Working With Panels*.
4. Click OK.

To Add a Launcher to an Empty Menu

To add a launcher to an empty menu, perform the following steps:

1. In a file manager window, access the menu where you want to add the launcher.
2. Choose File → New Launcher. A **Create Launcher** dialog is displayed.
3. Enter the properties of the launcher in the **Create Launcher** dialog. For more information on the elements in the **Create Launcher** dialog, see *Working With Panels*.
4. Click OK.

To Copy a Launcher to a Menu

To copy an existing launcher to a menu, perform the following steps:

1. In a file manager window, access the location from which you want to copy the launcher. For example, if you want to copy a launcher from the Applications menu, enter `applications:///` in the field on the location bar.
2. Select the launcher that you want to copy, then choose Edit → Copy File.
3. In a file manager window, access the location to which you want to copy the launcher.
4. Choose Edit → Paste Files. The launcher is added to the new location.

Alternatively, you can drag the launcher from one location to another.

The next time that you log out then log in again, the launcher is in the new menu location.

To Edit the Properties of a Menu

To edit the properties of a menu, perform the following steps:

1. Right-click on any item in the menu that you want to edit.
2. Choose Entire menu → Properties. A **Launcher Properties** dialog is displayed.
3. Modify the properties of the menu in the **Launcher Properties** dialog. For more information on the elements in the **Launcher Properties** dialog, see *Working With Panels*.
4. Click OK.

To Edit a Menu Item

To edit a menu item, perform the following steps:

1. Right-click on the item that you want to edit.
2. Choose Properties. A **Launcher Properties** dialog is displayed.
3. Modify the properties of the launcher in the **Launcher Properties** dialog. For more information on the elements in the **Launcher Properties** dialog, see *Working With Panels*.
4. Click OK.

To Delete an Item from a Menu

To delete an item from a menu, use the menu item popup menu. To delete an item from a menu, perform the following steps:

1. Right-click on the item that you want to delete.
2. Choose Remove this item.

Working With Windows

The information in this chapter describes how to use windows in the GNOME Desktop. You can use several types of window manager with the GNOME Desktop, for example, Metacity and Sawfish. Many of the functions in Metacity are also available in Sawfish. This chapter describes the functions that are associated with the Metacity window manager.

- “Windows and Workspaces” on page 81
- “Types of Window” on page 82
- “Menus and Applets for Working With Windows and Workspaces” on page 85
- “Manipulating Windows” on page 90
- “Manipulating Workspaces” on page 93

Windows and Workspaces

You can display many windows at the same time in the GNOME Desktop. Your windows are displayed in subdivisions of the GNOME Desktop that are called workspaces. A workspace is a discrete area in which you can work. Every workspace contains the same desktop, the same panels, and the same menus. However, you can run different applications, and open different windows in each workspace. You can display only one workspace at a time, but you can have windows open in other workspaces.

The Workspace Switcher applet displays a visual representation of your windows and workspaces, as show in Figure 6–1.



FIGURE 6-1 Workspace Switcher Applet

You can add workspaces at any time. To add workspaces to the GNOME Desktop, right-click on the Workspace Switcher applet, then choose Preferences. The **Workspace Switcher Preferences** dialog is displayed. Use the **Number of workspaces** spin box to specify the number of workspaces you require.

Window Manager Behavior

A window manager controls how windows appear and behave. The window manager manages where your windows are located, and which window has focus. The window frame contains buttons that enable you to perform standard actions such as moving, closing, and resizing windows.

You can set some window manager preferences in the Windows preference tool. This manual describes the functions that are associated with the default configuration of the Metacity window manager. The default configuration is specified in the Windows preference tool.


Types of Window

The GNOME Desktop features the following types of windows:

- Application windows

When you start an application, an application window opens. The window manager applies a frame to the application window. By default, the top edge of the application window contains a titlebar. The titlebar contains buttons that you can use to work with the window. The buttons in an application window frame enable you to perform actions such as open the Window Menu, or close the window. The Window Menu provides a number of actions that you can perform on the window.

The following figure shows a typical application window.



- Dialog windows


A dialog window is a popup window in which you enter information or commands. The dialog appears within a window frame.

You can use the top edge of the frame to work with the window. For example, you can use the titlebar to move the dialog. The frame also contains buttons that enable you to do the following:

- Open the Window Menu
- Close the dialog window

Typically, you open a dialog window from an application window. When you open a dialog window, the window is usually raised and has focus. Some dialog windows do not allow you to use the application until you close the dialog.

The following figure shows a typical dialog window.



Window Frames

A window frame is a border around a window. The window frame contains a titlebar. The titlebar contains buttons that you can use to work with the window.

Themes

You can apply several themes to your window frames. The theme determines how the frame looks. To choose a theme for all your window frames, use the Theme preference tool.

Control Elements

You can use the window frame to perform various actions with the window. In particular, the titlebar contains various buttons. The following figure shows the titlebar of an application window:



Dialog windows also contain some of the window frame control elements. Table 6-1 describes the active control elements on window frames, from left to right.

TABLE 6-1 Window Frame Control Elements

Control Element	Description
Window Menu button	Click on the button to open the Window Menu.
Titlebar	You can use the titlebar to perform the following actions: <ul style="list-style-type: none">■ To give focus to the window click on the titlebar.■ To move the window grab the titlebar and drag the window to the new location.■ To shade the window, double-click on the titlebar. To unshade the window, double-click on the titlebar again.

TABLE 6–1 Window Frame Control Elements (Continued)

Control Element	Description
Minimize button	Click on the Minimize button to minimize the window.
Maximize button	Click on the Maximize button to maximize the window.
Close Window button	Click on the Close Window button to close the window.
Border	The border around the window. Use the border to perform the following actions: <ul style="list-style-type: none">■ To resize the window grab the border and drag the border to the new size.■ To open the Window Menu, right-click on the border.
Window contents	The area inside the window frame. Use the window contents to perform the following actions: <ul style="list-style-type: none">■ To move a window, press-and-hold Alt, click in the window contents, then drag the window to the new location.■ To resize a window, press-and-hold Alt, then middle-click near the corner you want to resize. To resize the window, drag from the corner on which you middle-clicked.■ To open the Window Menu, press-and-hold Alt, then right-click in the window contents.

Menus and Applets for Working With Windows and Workspaces

This section describes the menus and applets that you can use to work with windows and workspaces.

Window Menu

— Minimize	Alt+F9
☐ Maximize	Alt+F10
Roll Up	Alt+F12
M Move	Alt+F7
R Resize	Alt+F8
× Close	Alt+F4
Put on All Workspaces	
Move to Workspace 1	
Move to Workspace 2	
Move to Workspace 3	
Move to Workspace 4	

The Window Menu is a menu of commands that you can use to perform actions on your windows. To open the Window Menu perform one of the following actions:

- Click on the Window Menu button on the window that you want to work with.
- Press Alt + spacebar.
- Press-and-hold Alt, then right-click on any part of the window that you want to work with.

Table 6–2 describes the commands and submenus in the Window Menu.

TABLE 6–2 Window Menu Commands and Submenus

Menu Item	Function
Minimize	Minimizes the window.
Maximize or Unmaximize	Maximizes the window. If the window is already maximized, choose Unmaximize to restore the window to its previous size.
Roll Up or Unroll	Reduces a window so that only the titlebar is visible. If the window is already rolled up, choose Unroll to restore the window to its previous size.
Move	Enables you to use the arrow keys to move the window.
Resize	Enables you to use the arrow keys to resize the window.
Close	Closes the window.
Put on All Workspaces or Only on This Workspace	Puts the window on all of your workspaces. If the window is already on all of your workspaces, choose Only on This Workspace to put the window on the current workspace only.
Move to <i>workspace-name</i> or Only on <i>workspace-name</i>	Moves the window to the workspace that you choose. If the window is on all of your workspaces, choose Only on <i>workspace-name</i> to put the window on the workspace that you want.

Window List Applet

Window List displays a button for each application window that is open. You can use the Window List to perform the following tasks:

- To minimize a window
Click on the button that represents the window.
- To restore a minimized window
Click on the button that represents the window.
- To give focus to a window
Click on the button that represents the window.

When you open an application window, Window List displays a button that represents the window. The window list buttons show which application windows are open. You can view which windows are open even if some windows are minimized, or other windows overlap a window. Window List can display buttons for the windows in your current workspace, or in all workspaces. To select this option, you must change the preferences of Window List.

You can also right-click on a window list button to open the Window Menu for the window that the button represents. When you open the Window Menu from Window List, the Window Menu does not contain the workspace commands. For more information on the Window Menu commands, see “Window Menu” on page 85.

Figure 6–2 shows Window List when the following windows are open:

- gedit
- Dictionary
- GHex
- GNOME Terminal



FIGURE 6–2 Window List Applet

The buttons in the applet show the status of your windows. Table 6–3 explains the information that the window list buttons provide about the window. The examples in Table 6–3 refer to Figure 6–2.

TABLE 6–3 Window Status Information on Window List Buttons

State	Indicates	Example
Button is pressed in.	The window has focus.	gedit

TABLE 6-3 Window Status Information on Window List Buttons *(Continued)*

State	Indicates	Example
Square brackets around window title.	The window is minimized.	[Dictionary]
Button is not pressed in, no square brackets around title.	The window is displayed, and is not minimized.	ghex
Numeral on button, in parentheses.	The button represents a group of buttons.	Gnome-terminal (3)

Grouping Buttons

Window List can group the buttons that represent windows in the same class under one window list button. The Gnome-terminal button in Figure 6-2 is an example of a button that represents a group of buttons. The following figure shows an example of Window List with a button group open:



To open a list of the windows in a group, click on the window list button that represents the group. You can click on the items in the list to give focus to windows, minimize windows, and restore windows.

To open the Window Menu for a window in a button group, right-click on the window list button that represents the group. A list of the windows in the group is displayed. To open the Window Menu for a window in the group, click on the item in the list. When you open the Window Menu from the Window List, the Window Menu does not contain the workspace commands. For more information on the Window Menu commands, see “Window Menu” on page 85.

Workspace Switcher Applet

Workspace Switcher displays a visual representation of your workspaces, as shown in Figure 6-3. Figure 6-3 shows the applet when the GNOME session contains four workspaces. Your workspaces appear as buttons on the applet. The background of the button in the applet that represents the current workspace is highlighted. The current workspace in Figure 6-3 is the workspace at the left of the applet. To switch to another workspace, click on the workspace in the applet.





FIGURE 6-3 Workspace Switcher Applet

Workspace Switcher also displays the application windows and dialogs that are open in your workspaces.

The applet displays the workspaces in order from left to right across the rows of the applet. In Figure 6-3, the applet is set up to display the workspaces in one row. You can specify the number of rows in which your workspaces are displayed in Workspace Switcher. You can also change the default behavior of the applet to display the names of your workspaces in the applet.

Using the Top Edge Panel to Work With Windows

From the top edge panel, you can view a list of all windows that are currently open. You can also choose a window to give focus to. To view the window list, click on the icon at the extreme right of the top edge panel. The following figure shows an example of the window list that is displayed from the top edge panel:



When the focus changes, the icon that you click on to display the window list changes. The icon represents the window that currently has focus. To give focus to a window, choose that window from the window list.

The window list lists the windows in all workspaces. The windows in all workspaces other than the current workspace, are listed under a separator line.

Manipulating Windows

This section describes how to manipulate windows.

To Give Focus to a Window

A window that has focus can receive input from the mouse and the keyboard. Only one window can have focus at a time. The window that has focus has a different appearance than other windows.

You can use the following elements to give focus to a window:

Element	Action
Mouse	Click on the window, if the window is visible.
Shortcut keys	Use shortcut keys to switch between the windows that are open. To give focus to a window, release the keys. The default shortcut keys to switch between windows are Alt + Tab.
Window List	Click on the button that represents the window in Window List.
Workspace Switcher	Click on the window that you want to give focus to in the Workspace Switcher display. If you click on a window in another workspace, Workspace Switcher switches to the new workspace, and gives focus to the window.
Top edge panel	Click on the icon at the extreme right of the top edge panel. A list of your open windows is displayed. Choose the window from the list.

To Minimize a Window

To minimize a window perform one of the following actions:

- Click on the Minimize button on the window frame.
- Open the Window Menu, then choose Minimize.
- If the window has focus, click on the button that represents the window in Window List. If the window does not have focus, click twice on the button that represents the window.
- Right-click on the button that represents the window in Window List, then choose Minimize from the popup menu.

To Maximize a Window

When you maximize a window, the window expands as much as possible. To maximize a window perform one of the following actions:

- To maximize the window, click on the Maximize button on the window frame. Alternatively, open the Window Menu, then choose Maximize.
- Right-click on the button that represents the window in Window List, then choose Maximize from the Window Menu.

To Restore a Window

To restore a maximized window perform one of the following actions:

- Click on the Maximize button on the window frame.
- Open the Window Menu. Choose Unmaximize.
- Right-click on the button that represents the window in Window List to open the Window Menu. Choose Unmaximize.

To restore a minimized window, click on the button that represents the window in Window List.

To Close a Window

To close a window perform one of the following actions:

- Click on the Close Window button on the window frame.
- Open the Window Menu. Choose Close.
- Right-click on the button that represents the window in Window List, then choose Close from the Window Menu.

If you have unsaved data in the window, you are prompted to save your data.

To Resize a Window

To resize a window perform one of the following actions:

- Point to a corner of the window. The mouse pointer changes to indicate that you can resize the window. Grab the corner and drag the window to the new size.
- Right-click on the button that represents the window in Window List. Choose Resize from the Window Menu. Use the arrow keys to resize the window.
- Press-and-hold Alt, then middle-click near the corner that you want to resize. The mouse pointer changes to indicate that you can resize from the corner. To resize the window, drag from the corner on which you middle-clicked.

- To resize a window horizontally point to one of the vertical edges of the window. The mouse pointer changes to indicate that you can resize the window. Grab the edge and drag the window to the new size.
- To resize a window vertically point to the bottom edge of the window. The mouse pointer changes to indicate that you can resize the window. Grab the edge and drag the window to the new size.

Note – You cannot resize some dialog windows. Also, some application windows have a minimum size below which you cannot reduce the window.

To Move a Window

To move a window perform one of the following actions:

- Grab the titlebar of the window and drag the window to the new location.
- Press-and-hold Alt, then drag the window to the new location.
- Open the Window Menu, then choose Move. Use the arrow keys to move the window to the new location.
- Right-click on the button that represents the window in Window List, then choose Move from the Window Menu. Use the arrow keys to move the window to the new location.

To Roll Up a Window

You can roll up and roll down windows, as follows:

- | | |
|-----------|--|
| Roll up | Reduce the window so that only the titlebar is visible. |
| Roll down | Switch a window from a rolled-up state so that the full window is displayed. |

To roll up a window perform one of the following actions:

- Double-click on the titlebar of the window. To roll down the window, double-click on the titlebar again.
- Open the Window Menu. Choose Roll Up. To roll down the window, choose Unroll.
- Right-click on the button that represents the window in Window List, then choose Roll Up from the Window Menu. To roll down the window, choose Unroll.

To Put a Window on All Workspaces

To put a window in all workspaces, open the Window Menu. Choose Put on All Workspaces. To set the window to appear only in the current workspace, choose Only on This Workspace.

To Move a Window to Another Workspace

You can move a window to another workspace in either of the following ways:

- Use Workspace Switcher
In the Workspace Switcher display, drag the window to the workspace you require.
- Use the Window Menu
Open the Window Menu. To move the window to the next workspace choose Move to *workspace-name*.

Manipulating Workspaces

This section describes how to manipulate workspaces.

To Switch Between Workspaces

You can switch between workspaces in any of the following ways:

- Use Workspace Switcher
Click on the workspace that you want to switch to in Workspace Switcher.
- Use shortcut keys
The default shortcut keys to switch between the workspaces are as follows:

Default Shortcut Keys	Function
Ctrl + Alt + right arrow	Selects the workspace to the right.
Ctrl + Alt + left arrow	Selects the workspace to the left.

To Add Workspaces

To add workspaces to the GNOME Desktop, right-click on Workspace Switcher, then choose Preferences. The **Workspace Switcher Preferences** dialog is displayed. Use the **Number of workspaces** spin box to specify the number of workspaces you require. Workspace Switcher adds new workspaces at the end of the workspace list.

To Name Workspaces

The default names of your workspaces are *Workspace 1*, *Workspace 2*, *Workspace 3*, and so on. To assign names to your workspaces, right-click on Workspace Switcher, then choose Preferences. The **Workspace Switcher Preferences** dialog is displayed. Use the **Workspaces names** list box to specify the names of your workspaces. Select a workspace, then type the new name for the workspace.

To Delete Workspaces

When you delete a workspace the windows in the workspace are moved to another workspace, and the empty workspace is deleted.

To delete workspaces from the GNOME Desktop, right-click on Workspace Switcher, then choose Preferences. The **Workspace Switcher Preferences** dialog is displayed. Use the **Number of workspaces** spin box to specify the number of workspaces you require. Workspace Switcher deletes workspaces from the end of the workspace list.

Nautilus File Manager

This chapter describes how to use the Nautilus file manager.

- “Introduction to Nautilus File Manager” on page 95
- “File Manager Windows” on page 96
- “Navigating Your Computer” on page 101
- “Managing Your Files and Folders” on page 109
- “Modifying the Appearance of Files and Folders” on page 117
- “Assigning Actions to Files” on page 123
- “Customizing the File Manager” on page 125
- “Using Removable Media” on page 130
- “Writing CDs” on page 133
- “Running Scripts From the File Manager” on page 134
- “Mounting and Unmounting a File System” on page 135
- “Using NFS Shares” on page 137

Introduction to Nautilus File Manager

The Nautilus file manager provides an integrated access point to your files and applications. The file manager enables you to do the following:

- Display your files and folders.
- Manage your files and folders.
- Run scripts.
- Customize your files and folders.
- Open special URI locations.
- Write data to a CD.

Nautilus also manages the desktop. The desktop lies behind all of the other components on your visible desktop. The desktop is an active component of the user interface.

File manager windows enable you to display and manage your files and folders. To open a file manager window, double-click on the **Documents** object on the desktop. The file manager window displays the contents of your default documents location in the view pane.

File Manager Windows

File manager windows enable you to display and manage your files and folders. Figure 7-1 shows a file manager window that displays the contents of a folder.




FIGURE 7-1 Contents of a Folder in a File Manager Window

Table 7-1 describes the components of file manager windows.

TABLE 7-1 File Manager Window Components

Component	Description
Menubar	Contains menus that you use to perform tasks in the file manager.
Toolbar	Contains buttons that you use to perform tasks in the file manager.
Location bar	Contains the following elements: <ul style="list-style-type: none">■ Location field or Go To field: Enables you to specify a file, folder, or URI that you want to view.■ Zoom buttons: Enable you to change the size of items in the view pane.■ View as drop-down list: Enables you to choose how to show items in your view pane.
Side pane	Performs the following functions: <ul style="list-style-type: none">■ Shows information about the current file or folder.■ Enables you to navigate through your files. <p>The side pane contains a drop-down list that enables you to choose what to show in the side pane. You can choose from the following options:</p> <ul style="list-style-type: none">■ Information■ Emblems■ History■ Notes■ Tree <p>To display the side pane, choose View → Side Pane.</p>
View pane	Shows the contents of the following: <ul style="list-style-type: none">■ Particular types of files■ Folders■ FTP sites■ Locations that correspond to special URIs
Statusbar	Displays status information.

You can also open a popup menu from file manager windows. To open this popup menu right-click in a file manager window. The items in this menu depend on where you right-click. For example, when you right-click on a file or folder, you can choose items related to the file or folder. When you right-click on the background of a view pane, you can choose items related to the display of items in the view pane.

Note – In other distributions of the GNOME Desktop, the Home toolbar button might have another designation, for example, Documents.

View Pane

The view pane can display the contents of the following:

- Particular types of files
- Folders
- FTP sites
- Locations that correspond to special URIs

The file manager contains *viewer components* that enable you to display particular types of file in the view pane. For example, you can use a text viewer to display text files in the view pane. Figure 7–2 shows a text file displayed in the view pane.



FIGURE 7-2 Text File in a File Manager Window

Displaying a file in the view pane provides the following benefits:

- Uses less system resources than when you launch an application.
- Takes less time than when you launch an application.

However, you cannot edit a file in the view pane.

The file manager also includes *views* that enable you to display the contents of your folders in different ways. For example, you can display the contents of a folder in the following types of view:

- Icon view: Shows the items in the folder as icons.
- List view: Shows the items in the folder as a list.

- **Audio view:** Shows only the audio items in the folder.

Use the View menu to choose how to display a folder. For more information on views, see “Using Views to Display Your Files and Folders” on page 119.

Side Pane

To display the side pane, choose View → Side Pane. You can choose what information you want to view in the side pane. You can choose to display one of the following:

- **Information**

Displays an icon that represents the current file or current folder. Also displays information about the current file or current folder. If a file is displayed in the view pane, buttons appear in the side pane. The buttons enable you to perform actions on a file, other than the default action.

- **Emblems**

Contains emblems that you can add to a file or folder. For more information on emblems, see the next section.

- **History**

Contains a history list of files, folders, FTP sites, and URIs that you have recently visited.

- **Notes**

Enables you to add notes to your files and folders.

- **Tree**

Displays a hierarchical representation of your file system. You can use the **Tree** to navigate through your files.

To close the side pane, click on the X button at the top right of the side pane.



Icons and Emblems

In icon view, the file manager displays your files and folders as icons. You can add emblems to your file icons and folder icons. An emblem is a small icon that you can add to an item to visually mark the item. For example, to mark a file as important, you can add an **Important** emblem to the file icon to create the following visual effect:



For more information on how to add an emblem to an icon, see “To Add an Emblem to a File or Folder” on page 117.




The following table describes the structure of the file icon:

Component	Description
	Emblem. This emblem is the Important emblem.
	Icon that represents the file. This icon might contain a preview of the contents of the file.
loremipsum.txt 2.7 K	Icon caption. You can modify what items of information are displayed in the icon caption.

The file manager includes default emblems for the following types of item:

- Symbolic links
- Items for which you have the following permissions:
 - Read permission only
 - No read permission and no write permission

The following table shows the default emblems:

Default Emblem	Description
	Symbolic link
	Read permission only
	No read permission and no write permission

Navigating Your Computer

Each file manager window displays the contents of a single file, folder, FTP site, or special URI location. This section describes the following:

- How to display items in file manager windows.
- How to open files from file manager windows.
- How to navigate the files and folders in your file system.
- How to navigate to FTP sites.
- How to access special URI locations.

To Display a Folder

You can display the contents of a folder in any of the following ways:

- Double-click on the folder in the view pane.
- In the **Location** field, type the path of the folder that you want to display, then press Return. The **Location** field includes an autocomplete feature. As you type a path, the file manager reads your file system. When you type enough characters to uniquely identify a directory, the file manager completes the name of the directory in the **Location** field.
- Use the **Tree** in the side pane. For more information, see “Using the Tree From the Side Pane” on page 102.
- Use the Back toolbar button and the Forward toolbar button to browse through your navigation history.

To change to the folder that is one level above the current folder, choose Go → Up. Alternatively, click on the Up toolbar button.

To reload the display, click on the Reload button.

If you cannot find the folder that you want to display, you can use Search Tool. To start Search Tool, choose Find Files from the Main Menu.

Using the Tree From the Side Pane

The **Tree** displays a hierarchical representation of your file system. The **Tree** provides a convenient way to navigate your file system. To display the **Tree** in the side pane, choose Tree from the drop-down list at the top of the side pane.

In the **Tree**, folders are represented as follows:

Folder State	Graphic Representation
Closed folder	Right arrow
Open folder	Down arrow

Table 7–2 describes the tasks that you can perform with the **Tree**, and how to perform the tasks.

TABLE 7–2 Tree Tasks

Task	Action
Open the Tree .	Choose Tree from the drop-down list at the top of the side pane.
Close the Tree .	Choose another item from the drop-down list at the top of the side pane.
Open a folder in the Tree .	Click on the arrow next to the folder in the Tree .
Close a folder in the Tree .	Click on the arrow next to the folder in the Tree .
Display the contents of a folder in the view pane.	Select the folder in the Tree .
Display the contents of a file in the view pane.	Select the file in the Tree .

You can set your preferences so that the **Tree** does not display files. For more information, see “To Set Views Preferences” on page 125.

Opening Files

When you open a file, the file manager performs the default action for that file type. The default action can be one of the following:

- Use a viewer component to display the file in the view pane.
- Launch an application that opens the file.

The file manager checks the contents of a file to determine the type of a file. If the first lines do not determine the type of the file, then the file manager checks the file extension.

If you cannot find the file that you want to open, you can use Search Tool. To start Search Tool, choose Find Files from the Main Menu.

Viewing Files in the View Pane

The file manager contains viewer components that enable you to display particular types of file in the view pane. For example, you can display the following types of files in the view pane:

- Plain text files
- PNG files
- Joint Photographic Experts Group (JPEG) files

To reload the contents of the view pane, choose View → Reload. To stop loading an item in the view pane, choose View → Stop.

When you display a file in the view pane, the viewer component might add menu items to the file manager menus. The menu items relate to the file type that is displayed. For example, when you display a PNG file, the Edit menu contains flip and rotate menu items.

Also, when you display some types of file in the view pane, you can use the file manager zoom buttons to change the size of the item.

To Execute the Default Action

To execute the default action for a file, double-click on the file. For example, if the default action for plain text documents is to display the file in a text viewer. In this case, you can double-click on the file to display the file in a text viewer.

You can set your file manager preferences so that you click once on a file to execute the default action. For more information, see “To Set Behavior Preferences” on page 126.

To Execute Non-Default Actions Using the Open With Submenu

To execute actions other than the default action for a file, perform the following steps:

1. In the view pane, select the file that you want to perform an action on. Choose File → Open With. The Open With submenu opens. The items in this submenu correspond to the contents of the following parts of the File Associations preference tool:
 - **Default action** drop-down list in the **Edit file type** dialog
 - **Viewer component** drop-down list in the **Edit file type** dialog
2. Choose an action from the Open With submenu.

To Execute Other Actions When Displaying a File

When you display a file in the view pane, the side pane might contain buttons. Figure 7-2 shows the buttons in the side pane when a text file is displayed in the view pane.

The buttons represent any actions that are defined in the File Associations preference tool. The actions are defined in the **Default action** drop-down list in the **Edit file type** dialog in the File Associations preference tool. Click on a button to execute an action. For example, if an action defined for plain text documents is to open the file in the gedit text editor. If this action is defined, an Open with gedit button is displayed in the side pane. To open the file in the gedit application, click on the Open with gedit button.

Note – A button that represents the action does not appear in the side pane if the actions are excluded in either of the following dialogs:

- **Open with Other Application**
 - **Open with Other Viewer**
-

To Access FTP Sites

You can use the file manager to access FTP sites. To access an FTP site, enter the URL for the site in the field on the location bar, then press Return. The contents of the site are displayed in the view pane. To copy a file from the FTP site, drag the file to the new location.

To access an FTP site that requires a username and password, you can enter the URL in the following form:

`ftp://username:password@hostname.domain`

To reload the FTP site in the view pane, choose View → Reload. To stop loading the FTP site, choose View → Stop.

To Access Network Places

If your system is configured to access places on a network, you can use the file manager to access the network places.

To access network places, open the file manager and choose Go → Network Places. A file manager window is displayed. The window displays the network places that you can access. Double-click on the network place that you want to access.

To access UNIX shares, double-click on the **Unix Network (NFS)** object. A list of the UNIX shares available to you is displayed in the file manager window.

To access Windows shares, double-click on the **Windows Network (SMB)** object. A list of the Windows shares available to you is displayed in the file manager window.

To Add a Network Place

To add a network place, perform the following steps:

1. Open the file manager and choose Go → Network Places. A file manager window is displayed.
2. Double-click on the **Add Network Place** object. The **Add Network Place** dialog is displayed. Enter the details of the server in the dialog, as follows:

Dialog Element	Description
Location	Use this text box to specify the location that you want to add. Alternatively, select one of the following locations from the drop-down list: <ul style="list-style-type: none">■ FTP Server■ Web Folder■ Windows Network (SMB)■ Unix Network (NFS)
Shortcut name	Use this text box to specify a shortcut name for the network place.
Anonymous login	FTP Server option only. Select this option to log in to the FTP server as an anonymous user.
No login required	Web Folder, Windows Network (SMB), and Unix Network (NFS) options only. Select this option if you do not need to log in to the web folder, Windows share, or UNIX share.

Dialog Element	Description
Username	Use this text box to specify a username when you connect to the specified network place. When you connect to the network place, you must enter your password.
Go there now	Select this option if you want to access the network place immediately.

3. Click OK to add your network place.

Accessing Special URI Locations

The GNOME Desktop contains special URI locations that enable you to access particular functions from the file manager. For example, to access the preference tools, you can access the `preferences:///` URI in a file manager window. Table 7-3 lists the special URI locations that you can use with the file manager.

TABLE 7-3 Special URI Locations

URI Location	Description
<code>applications:///</code>	Displays a list of the applications in the GNOME Desktop. The applications are the same as the applications in the Applications menu. To open an application, double-click on the application.
<code>burn:///</code>	Copy files and folders that you want to write to a CD to this location. You can write the contents of this location to a CD.
<code>fonts:///</code>	Displays all the fonts that are available in your system. To preview a font, double-click on the font. You can also use this location to add fonts to the GNOME Desktop.
<code>network:///</code>	Displays the Network Places location. Network Places displays network locations to which you can connect, if your system is configured to access locations on a network. To access a network location, double-click on the network location. You can also use this URI to add network locations to your system.
<code>nfs:///</code>	Displays UNIX NFS network locations, if your system is configured to access UNIX NFS locations. To access a NFS location, double-click on the NFS location.

TABLE 7-3 Special URI Locations (Continued)

URI Location	Description
<code>preferences:///</code>	Displays a list of the preference tools in the GNOME Desktop. The preference tools are the same as the preference tools in the Preferences menu. To open a preference tool, double-click on the preference tool.
<code>printers:///</code>	Displays printers, if your system is configured to access printers. To access a printer, double-click on the printer. You can also use this URI to add printers to your system.
<code>smb:///</code>	Displays Windows servers, if your system is configured to access Windows servers. To open a Windows server, double-click on the Windows server.
<code>system-settings:///</code>	Displays a list of applications that you can use to modify your system settings.

Using Your Navigation History

The file manager maintains a history list of files, folders, FTP sites, and URI locations. You can use the history list to navigate to files, folders, FTP sites, and URI locations that you have recently visited. Your history list contains the last ten items that you viewed. The following sections describe how to navigate your history list.

To clear your history list choose Go → Clear History.

To Navigate Your History List Using the Go Menu

To display a list of previously-viewed items, choose the Go menu. Your history list is displayed in the lower part of the Go menu. To open an item in your history list, choose the item from the Go menu.

To Navigate Your History List Using the Toolbar

To use the toolbar to navigate your history list, perform one of the following actions:

- To open the previous file, folder, or URI in your history list, click on the Back toolbar button.
- To open the next file, folder, or URI in your history list, click on the Forward toolbar button.
- To display a list of previously-viewed items, click on the down arrow to the right of the Back toolbar button. To open an item from this list, click on the item.
- To display a list of items that you viewed after you viewed the current item, click on the down arrow to the right of the Forward toolbar button. To open an item from this list, click on the item.

To Navigate Your History List Using History in the Side Pane

To display the **History** list in the side pane, choose **History** from the drop-down list at the top of the side pane. The **History** list in the side pane displays a list of your previously-viewed items.

To display an item from your history list in the view pane, click on the item in the **History** list.

To Bookmark Your Favorite Locations

To access an item in your bookmarks, choose the item from the Bookmarks menu. You can add your favorite locations to your Bookmarks menu. You can add bookmarks to files and folders in your file system, to FTP sites, or to URI locations.

To Add a Bookmark

To add a bookmark, display the item that you want to bookmark in the view pane. Choose Bookmarks → Add Bookmark.

To Edit a Bookmark

To edit your bookmarks perform the following steps:

1. Choose Bookmarks → Edit Bookmarks. An **Edit Bookmarks** dialog is displayed.
2. To edit a bookmark, select the bookmark on the left side of the **Edit Bookmarks** dialog. Edit the details for the bookmark on the right side of the **Edit Bookmarks** dialog, as follows:

Dialog Element	Description
Name	Use this text box to specify the name that identifies the bookmark in the Bookmarks menu.
Location	Use this field to specify the location of the bookmark.

3. To delete a bookmark, select the bookmark on the left side of the dialog. Click **Delete**.

Managing Your Files and Folders

This section describes how to work with your files and folders.

Drag-and-Drop in the File Manager

You can use drag-and-drop to perform several tasks in the file manager. When you drag-and-drop, the mouse pointer provides feedback about the task that you perform. Table 7-4 describes the tasks that you can perform with drag-and-drop. The table also shows the mouse pointers that appear when you drag-and-drop.

TABLE 7-4 Drag-and-Drop in the File Manager





Task	Action	Mouse Pointer
Move an item	Drag the item to the new location.	
Copy an item	Grab the item, then press-and-hold Ctrl. Drag the item to the new location.	
Create a symbolic link to an item	Grab the item, then press-and-hold Ctrl + Shift. Drag the item to the location where you want the symbolic link to reside.	

TABLE 7-4 Drag-and-Drop in the File Manager (Continued)

Task	Action	Mouse Pointer
Ask what to do with the item you drag	<p>Grab the item, then press-and-hold Alt. Drag the item to the location where you want the item to reside. Release the mouse button. A popup menu appears. Choose one of the following items from the popup menu:</p> <ul style="list-style-type: none"> ■ Move here Moves the item to the location. ■ Copy here Copies the item to the location. ■ Link here Creates a symbolic link to the item at the location. ■ Set as Background If the item is an image, sets the image to be the desktop background. You can use this command to set the desktop background and the view pane background. ■ Cancel Cancels the drag-and-drop operation. 	

To Select Files and Folders

You can select files and folders in several ways in the file manager. Table 7-5 describes how to select items in file manager windows and on the desktop.

TABLE 7-5 Selecting Items in the File Manager

Task	Action
Select an item	Click on the item.
Select a group of contiguous items	<p>In icon view, drag around the files that you want to select.</p> <p>In list view, click on the first item in the group. Press-and-hold Shift, then click on the last item in the group.</p>
Select multiple items	<p>Press-and-hold Ctrl. Click on the items that you want to select.</p> <p>Alternatively, press-and-hold Ctrl, then drag around the files that you want to select.</p>
Select all items in a folder	Choose Edit → Select All Files.

To perform the default action on an item, double-click on the item. You can set your file manager preferences so that you click once on a file to execute the default action. For more information, see “To Set Behavior Preferences” on page 126.

To Move a File or Folder

The following sections describe the ways that you can move a file or folder.

Drag to the New Location in a View Pane

To drag a file or folder to a new location in a view pane, perform the following steps:

1. Open a file manager window. Choose File → New Window to open a second file manager window.
2. In one window, select the folder from which you want to move the file or folder. In the other window, select the folder to which you want to move the file or folder.
3. Drag the file or folder that you want to move to the new location in the other window.

To move the file or folder to a folder that is one level below the current location, do not open a new window. Instead, drag the file or folder to the new location in the same window.

Cut and Paste to the New Location

You can cut a file or folder and paste the file or folder into another folder, as follows:

1. Select the file or folder that you want to move, then choose Edit → Cut File.
2. Open the folder to which you want to move the file or folder, then choose Edit → Paste Files.

To Copy a File or Folder

The following sections describe the ways you can copy a file or folder.

Drag to the New Location in a View Pane

To copy a file or folder perform the following steps:

1. Open a file manager window. Choose File → New Window to open a second file manager window.
2. In one window, select the folder from which you want to copy the file or folder. In the other window, select the folder to which you want to copy the file or folder.
3. Grab the file or folder, then press-and-hold Ctrl. Drag the file or folder to the new location in the other window.

To copy the file or folder to a folder that is one level below the current location, do not open a new window. Instead, grab the file or folder, then press-and-hold Ctrl. Drag the file or folder to the new location in the same window.

Copy and Paste to the New Location

You can copy a file or folder and paste the file or folder into another folder, as follows:

1. Select the file or folder that you want to copy, then choose Edit → Copy File.
2. Open the folder to which you want to copy the file or folder, then choose Edit → Paste Files.

To Duplicate a File or Folder

To create a copy of a file or folder in the current folder perform the following steps:

1. Select the file or folder that you want to duplicate in the view pane.
2. Choose Edit → Duplicate. Alternatively, right-click on the file or folder in the view pane, then choose Duplicate.

A copy of the file or folder appears in the current folder.

To Create a Folder

To create a folder perform the following steps:

1. Select the folder where you want to create the new folder.
2. Choose File → New Folder. Alternatively, right-click on the background of the view pane, then choose New Folder.

An **untitled** folder is added to the view pane. The name of the folder is selected.

3. Type a name for the folder, then press Return.

To Rename a File or Folder

To rename a file or folder perform the following steps:

1. Select the file or folder that you want to rename in the view pane.
2. Choose Edit → Rename. Alternatively, right-click on the file or folder in the view pane, then choose Rename.

The name of the file or folder is selected.

3. Type a new name for the file or folder, then press Return.

To Move a File or Folder to Trash

To move a file or folder to **Trash** perform the following steps:

1. Select the file or folder that you want to move to **Trash** in the view pane.

2. Choose Edit → Move to Trash. Alternatively, right-click on the file or folder in the view pane, then choose Move to Trash.

Alternatively, you can drag the file or folder from the view pane to the **Trash** object on the desktop.

Note – When you move a file or folder from a removable media to **Trash**, the file or folder is stored in a **Trash** location on the removable media. To remove the file or folder permanently from the removable media, you must empty **Trash**.

To Delete a File or Folder

When you delete a file or folder, the file or folder is not moved to **Trash**, but is deleted from your file system immediately. The Delete menu item is only available if you select the **Include a Delete command that bypasses Trash** option in the **Folder Options** dialog.

To delete a file or folder perform the following steps:

1. Select the file or folder that you want to delete in the view pane.
2. Choose Edit → Delete. Alternatively, right-click on the file or folder in the view pane, then choose Delete.

To Create a Symbolic Link to a File or Folder

A symbolic link is a special type of file that points to another file or folder. When you perform an action on a symbolic link, the action is performed on the file or folder to which the symbolic link points. However, when you delete a symbolic link, you delete the link file, not the file to which the symbolic link points.

To create a symbolic link to a file or folder, select the file or folder to which you want to create a link. Choose Edit → Make Link. A link to the file or folder is added to the current folder.

Alternatively, grab the item to which you want to create a link, then press-and-hold Ctrl + Shift. Drag the item to the location where you want to place the link.

By default, the file manager adds an emblem to symbolic links.

Note – The permissions of a symbolic link are determined by the file or folder to which a symbolic link points.

To View the Properties of a File or Folder

To view the properties of a file or folder, perform the following steps:

1. Select the file or folder whose properties you want to view.
2. Choose File → Properties. A properties dialog is displayed.
3. Use the properties dialog to view the properties of the file or folder.
4. Click Close to close the properties dialog.

To Change Permissions

Permissions are settings assigned to each file and folder that determine what type of access users can have to the file or folder. The following table lists the permissions that you can set for files and folders, and the effect of the permission on files and folders:

Permission	File	Folder
Read	Permission to read the file.	Permission to list the contents of the folder.
Write	Permission to make changes to the file.	Permission to create and delete files in the folder.
Execute	Permission to run the file as a program. This is only relevant if the file is a program or script.	Permission to access files in the directory.

You can set permissions for different types of user. The following table lists the types of user that you can set for which you can set permissions:

User Category	Description
Owner	The user that created the file or folder.
Group	The group to which the owner belongs.
Others	All other users who are not in the group to which the owner belongs.

To change the permissions on a file or folder perform the following steps:

1. Select the file or folder that you want to change.
2. Choose File → Properties. A properties dialog is displayed.
3. Click on the **Permissions** tab. In the **Permissions** tabbed section, use the drop-down lists and check boxes to change the permissions for the file or folder. The following table describes the dialog elements on the **Permissions** tabbed section:

Element	Description
File owner	To change the owner of the file or folder, select the owner from the drop-down list.
File group	To change the group to which a file or folder belongs, select the group from the drop-down list.
Owner	Select the permissions that you want to apply to the owner of the file or folder.
Group	Select the permissions that you want to apply to the group to which the owner of the file or folder belongs.
Others	Select the permissions that you want to apply to all other users who are not in the group to which the owner belongs.
Text view	Displays the permissions that you select from the Read , Write , and Execute options, in text format.
Number view	Displays the permissions that you select from the Read , Write , and Execute options, in text format.
Last changed	Displays the date and time that the file or folder was last modified.

4. Click Close to close the properties dialog.

Adding Notes to Files and Folders

You can add notes to files or folders. You can add notes to files or folders in the following ways:

- From the properties dialog
- From **Notes** in the side pane

To Add a Note Using the Properties Dialog

To add a note to a file or folder, perform the following steps:

1. Select the file or folder to which you want to add a note.
2. Choose File → Properties. A properties dialog is displayed.
3. Click on the **Notes** tab. In the **Notes** tabbed section, type the note.
4. Click Close to close the properties dialog. A note emblem is added to the file or folder.

To delete a note, delete the note text from the **Notes** tabbed section.

To Add a Note Using Notes in the Side Pane

To add a note to a file or folder, perform the following steps:

1. Open the file or folder to which you want to add a note in the view pane.
2. Choose **Notes** from the drop-down list at the top of the side pane. To display the side pane, choose View → Side Pane.
3. Type the note in the side pane. A note emblem is added to the file or folder in the view pane, and a note icon is added to the side pane. You can click on this icon to display the note.

To delete a note, delete the note text from **Notes** in the side pane.

Using Trash

You can move the following items to **Trash**:

- Files
- Folders
- Desktop objects

If you need to retrieve a file from **Trash**, you can display **Trash** and move the file out of **Trash**. When you empty **Trash**, you delete the contents of **Trash** permanently.

To Display Trash

You can display the contents of **Trash** in the following ways:

- From a file manager window
Choose Go → Trash. The contents of **Trash** are displayed in the window.
- From the desktop
Double-click on the **Trash** object on the desktop.

To Empty Trash

You can empty the contents of **Trash** in the following ways:

- From a file manager window
Choose File → Empty Trash.
- From the desktop
Right-click on the **Trash** object, then choose Empty Trash.

Modifying the Appearance of Files and Folders

The file manager enables you to modify the appearance of your files and folders in several ways, as described in the following sections.

To Add an Emblem to a File or Folder

To add an emblem to an item perform the following steps:

1. Select the item to which you want to add an emblem.
2. Right-click on the item, then choose Properties. A properties dialog is displayed.
3. Click on the **Emblems** tab to display the **Emblems** tabbed section.
4. Select the emblem to add to the item.
5. Click Close to close the properties dialog.

To Add a New Emblem

To add a new emblem, perform the following steps:

1. Choose Edit → Backgrounds and Emblems.
2. Click on the Emblem button, then click on the Add a New Emblem button. A **Create a New Emblem** dialog is displayed.
3. Type a name for the emblem in the **Keyword** text box.
4. Click on the **Image** button. A dialog is displayed. , click Browse. When you choose an emblem, click OK.
5. Click OK on the **Create a New Emblem** dialog.

To Change the Icon for a File or Folder

To change the icon that represents an individual file or folder, perform the following steps:

1. Select the file or folder that you want to change.
2. Choose File → Properties. A properties dialog is displayed.
3. On the **Basic** tabbed section, click on the Select Custom Icon button. A **Select an icon** dialog is displayed.

4. Use the **Select an icon** dialog to choose the icon to represent the file or folder.
5. Click Close to close the properties dialog.

To restore an icon from a custom icon to the default icon specified in the File Associations preference tool, right-click on the icon then choose Remove Custom Icon. Alternatively, click on the **Remove Custom Icon** button on the **Properties** dialog.

To change the icon that represents a file type, use the File Associations preference tool.




To Change the Size of Items in a View

You can change the size of items in a view. You can change the size if the view displays a file or a folder. You can change the size of items in a view in the following ways:

- To enlarge the size of items in a view, choose View → Zoom In.
- To reduce the size of items in a view, choose View → Zoom Out.
- To return items in a view to the normal size, choose View → Normal Size.

You can also use the zoom buttons on the location bar to change the size of items in a view. Table 7-6 describes how to use the zoom buttons.

TABLE 7-6 Zoom Buttons

Button	Button Name	Description
	Zoom Out button	Click on this button to reduce the size of items in a view.
	Normal Size button	Click on this button to return items in a view to normal size.
	Zoom In button	Click on this button to enlarge the size of items in a view.

The file manager remembers the size of items in a particular folder. The next time that you display the folder, the items are displayed in the size that you selected. In other words, when you change the size of items in a folder, you customize the folder to display the items at that size. To return the size of the items to the default size specified in your preferences, choose View → Reset View to Defaults.

Using Views to Display Your Files and Folders

The file manager provides several ways to display the contents of your files. The file manager includes viewer components that enable you to display particular types of file in the view pane. For example, you can use a web page viewer to display HTML files in the view pane. You can use a text viewer to view plain text files in the view pane.

You can also use the file manager to open a file in an appropriate application. For more information, see “Opening Files” on page 103.

The file manager includes views that enable you to show the contents of your folders in different ways. For example, you can show the contents of a folder in the following types of view:

- **Icon view**
Shows the items in the folder as icons. Figure 7-1 shows a folder in icon view.
- **List view**
Shows the items in the folder as a list. Figure 7-3 shows a folder in list view.




FIGURE 7-3 File Manager Window in List View

- **Audio view**
Shows the audio items in the folder only, and displays controls that enable you to play the audio files. Figure 7-4 shows a folder in audio view.




FIGURE 7-4 File Manager Window in Audio View

Use the **View** menu to choose how to display a file or folder. You can also use the **View as** drop-down list to choose how to display a file or folder. When you display a folder, you can specify how you want to arrange or sort items in the folder. You can modify the size of the items in the view pane. The following sections describe how to work with icon view, list view, and views of files.

To Choose a View in Which to Display a File or Folder

Choose the type of view in which to display the contents of a file or folder from the **View** menu.

Alternatively, to choose a view, choose **View** → **View as**. Select the view that you want to use from the **Open with Other Viewer** dialog, then click on the **Choose** button.

You can also choose the type of view from the **View as** drop-down list. The **View as** drop-down list is located at the right side of the location bar.

You can display different folders in different views. The file manager remembers the view that you choose for a particular folder. The next time that you display the folder, the file manager displays the folder in that view. To return the view for the folder to the default view specified in your preferences, choose **View** → **Reset View to Defaults**.

To Arrange Your Files in Icon View

When you display the contents of a folder in icon view, you can specify how to arrange the items in the folder. To specify how to arrange items in icon view, choose **View** → **Arrange Items**. The **Arrange Items** submenu contains the following sections:

- The top section contains an option that enables you to arrange your files manually.
- The middle section contains options that enable you to sort your files automatically.
- The bottom section contains options that enable you to modify how your files are arranged.

Choose the appropriate options from the submenu, as described in the following table:

Option	Description
Manually	Select this option to arrange the items manually. To arrange the items manually, drag the items to the location you require within the view pane.
By Name	Select this option to sort the items alphabetically by name. The order of the items is not case sensitive. If the file manager is set to display hidden files, the hidden files are shown last.
By Size	Select this option to sort the items by size, with the largest item first. When you sort items by size, the folders are sorted by the number of items in the folder. The folders are not sorted by the total size of the items in the folder.
By Type	Select this option to sort the items alphabetically by object type. The items are sorted alphabetically by the description of their <i>MIME type</i> in the File Associations preference tool. The MIME type identifies the format of a file, and enables applications to read the file. For example, an email application can use the <code>image/png</code> MIME type to detect that a PNG file is attached to an email.
By Modification Date	Select this option to sort the items by the date the items were last modified. The most recently modified item is first.
By Emblems	Select this option to sort the items by any emblems that are added to the items. The items are sorted alphabetically by emblem name. Items that do not have emblems are last.
Compact Layout	Select this option to arrange the items so that the items are closer to each other.
Reversed Order	Select this option to reverse the order of the option by which you sort the items. For example, if you sort the items by name, select the Reversed Order option to sort the items in reverse alphabetical order.

The file manager remembers how you arrange the items in a particular folder. The next time that you display the folder, the items are arranged in the way that you selected. In other words, when you specify how to arrange the items in a folder, you customize the folder to display the items in that way. To return the arrangement settings of the folder to the default arrangement settings specified in your preferences, choose View → Reset View to Defaults.

To Resize an Icon in Icon View

In icon view, you can change the size of the icon that represents an item that is displayed. To change the size of an item in icon view, perform the following steps:

1. Right-click on the item that you want to resize, then choose **Stretch Icon**. A rectangle appears around the item, with a handle at each corner.
2. Grab one of the handles, then drag the icon to the size that you want.
To return the icon to the original size, right-click on the icon, then choose **Restore Icon's Original Size**.

You can also resize objects on the desktop.

To Modify the Behavior of a View

You can modify the behavior of a view in the following ways:

- Specify that the view is the default view for a particular file or folder.
- Specify that the view is the default view for a file type or all folders.
- Specify that the view is an item in the View as submenu for a particular file or folder.
- Specify that the view is an item in the View as submenu for all of a particular file type or for all folders.
- Specify that the view is not an item in the View as submenu for a particular file or folder.

To modify the behavior of a view perform the following steps:

1. Choose **View** → **View as**. An **Open with Other Viewer** dialog is displayed.
2. Select the view that you want to modify from the table in the dialog.
3. Click on the **Modify** button. A **Modify** dialog is displayed. The following table describes the options on the **Modify** dialog:

Option	Description
Include in the menu for <i>item-name</i> items	Select this option to include the view in the View as submenu for this type of item.
Use as default for <i>item-name</i> items	Select this option to use the view as the default for this type of item.
Include in the menu for <i>item-name</i> only	Select this option to include the view in the View as submenu for this item only.
Use as default for <i>item-name</i> only	Select this option to use the view as the default for this item only.

Option	Description
Don't include in the menu for <i>item-name</i> items	Select this option to exclude the view from the View as submenu for this type of item.

4. Click OK, then click Cancel to close the **Open with Other Viewer** dialog.

Note – You can also modify the actions that are associated with a file type in the **Edit file type** dialog in the File Associations preference tool. To open the **Edit file type** dialog, click on the Go There button.

Assigning Actions to Files

When you open a file, the file manager performs the default action for that file type. The File Associations preference tool contains a table of file types, their associated file extensions, and their default actions. This table specifies what happens when you double-click on a file in the file manager.

You can also use the file manager to modify the actions that are associated with a particular file or file type.

You can use the File Associations preference tool to perform the following tasks:

- Specify the default action for a file type. You can also change the default action for a file type in the file manager.
- Associate a file type with one or more applications. The default action might specify to open the file in an application that is associated with the file type.
- Associate a file type with one or more viewers. The default action might specify to open the file in a viewer that is associated with the file type.
- Associate a file extension with a MIME type. The MIME type specifies the format of the file so that Internet browsers and email applications can read the file.

To Modify Actions

You can modify the actions associated with a file or file type. You can do the following:

- Specify that the action is the default action for a particular file.
- Specify that the action is the default action for a particular file type.
- Specify that the action is an item in the Open With submenu for a particular file.

- Specify that the action is an item in the Open With submenu for a particular file type.
- Specify that the action is not an item in the Open With submenu for a particular file type.

To modify the actions associated with a file or file type, perform the following steps:

1. In the view pane, select the file for which you want to modify an action. If you want to modify an action associated with a file type, select a file of that type.
2. Choose File → Open With. Perform either of the following steps:
 - Choose Other Application. An **Open with Other Application** dialog is displayed.
 - Choose Other Viewer. An **Open with Other Viewer** dialog is displayed.
3. From the table in the dialog, select the application or viewer for which you want to modify the behavior.
4. Click on the Modify button. A **Modify** dialog is displayed. The following table describes the options on the **Modify** dialog:

Option	Description
Include in the menu for <i>filetype</i> items	Select this option to include the application or viewer in the Open With submenu for this file type.
Use as default for <i>filetype</i> items	Select this option to use the application or viewer as the default action for this file type.
Include in the menu for <i>filename</i> only	Select this option to include the application or viewer in the Open With submenu for this file, and not for other files of this type.
Use as default for <i>filename</i> only	Select this option to use the application or viewer as the default action for this file, and not for other files of this type.
Don't include in the menu for <i>filetype</i> items	Select this option to exclude the application or viewer from the Open With submenu for this file type.

5. Click OK, then click Cancel to close the dialog.

Note – You can also modify the actions that are associated with a file type in the **Edit file type** dialog in the File Associations preference tool. To open the **Edit file type** dialog, click on the Go There button.

Customizing the File Manager

You can customize the file manager to suit your requirements and preferences. This section describes how to customize the file manager.

Setting Your Preferences

Use the **Folder Options** dialog to set preferences for the file manager. To display the **Folder Options** dialog, choose Edit → Preferences.

You can set preferences in the following categories:

- The default settings for views.
- The behavior of files and folders, executable text files, and **Trash**.
- The information that is displayed in icon captions.
- Preview options to improve the performance of the file manager.

To Set Views Preferences

You can specify a default view, and select sort options and display options. You can also specify default settings for icon views and list views. To specify your default view settings, choose Edit → Preferences. Click on the **Views** tab to display the **Views** tabbed section.

Table 7–7 lists the views preferences that you can modify.

TABLE 7–7 Views Preferences

Dialog Element	Description
View new folders using	Select the default view for folders. When you open a folder, the folder is displayed in the view that you select.
Arrange items	Select the characteristic by which you want to sort the items in folders that are displayed in this view.
Sort folders before files	Select this option to list folders before files when you sort a folder.
Sort in reverse	Select this option if you want to reverse the order by which items are sorted in this view. If you select this option, the order of the characteristic you select in the Arrange Items drop-down list is reversed. For example, if you select By Name , the items are sorted in reverse alphabetical order.

TABLE 7-7 Views Preferences *(Continued)*

Dialog Element	Description
Show hidden and backup files	Select this option to display hidden files and backup files in the view pane. The first character in a hidden filename is a period (.). The last character in a backup filename is a tilde (~).
Default zoom level	Icon view and list view. Select the default zoom level for folders that are displayed in this view. The zoom level specifies the size of items in a view.
Use compact layout	Select this option to arrange the items in icon view so that the items in the folder are closer to each other.
Text beside icons	Select this option to place the icon captions for items beside the icon rather than under the icon.
Use manual layout	Select this option if you want to arrange the items in icon view manually.
Show only folders	Select this option to display only folders in the Tree in the side pane.

To Set Behavior Preferences

To set your preferences for files and folders, choose **Edit** → **Preferences**. Click on the **Behavior** tab to display the **Behavior** tabbed section.

Table 7-8 lists the preferences that you can modify for files and folders.

TABLE 7-8 File and Folder Behavior Preferences

Option	Description
Single click to activate items	Select this option to perform the default action for an item when you click on the item. When this option is selected, and you point to an item, the title of the item is underlined.
Double click to activate items	Select this option to perform the default action for an item when you double-click on the item.
Open activated item in a new window	Select this option to open a new window when you open a file or folder.
Run executable files when they are clicked	Select this option to run an executable file when you choose the executable file. An executable file is a text file that can execute, that is, a shell script.
View executable files when they are clicked	Select this option to display the contents of an executable file when you choose the executable file.

TABLE 7-8 File and Folder Behavior Preferences (Continued)

Option	Description
Ask each time	Select this option to display a dialog when you choose an executable file. The dialog asks whether you want to execute the file or display the file.
Ask before emptying the Trash or deleting files	Select this option to display a confirmation message before Trash is emptied, or files are deleted.
Include a Delete command that bypasses Trash	Select this option to add a Delete menu item to the following menus: <ul style="list-style-type: none">■ The Edit menu.■ The popup menu that is displayed when you right-click on a file, folder, or desktop object. When you select an item then choose the Delete menu item, the item is deleted from your file system immediately.

To Set Icon Captions Preferences

An icon caption displays the name of a file or folder in an icon view. The icon caption also includes three additional items of information on the file or folder. The additional information is displayed after the file name. Normally only one item of information is visible, but when you zoom in on an icon, more of the information is displayed. You can modify what additional information is displayed in icon captions.

To set your preferences for icon captions, choose Edit → Preferences. Click on the **Icon Caption** tab to display the **Icon Caption** tabbed section.

Select the items of information that you want to display in the icon caption from the three drop-down lists. Select the first item from the first drop-down list, select the second item from the second drop-down list, and so on. The following table describes the items of information that you can select:

Information	Description
Size	Choose this option to display the size of the item.
Type	Choose this option to display the description of the MIME type of the item from the File Associations preference tool.
Date modified	Choose this option to display the last modification date of the item.
Date accessed	Choose this option to display the date that the item was last accessed.
Owner	Choose this option to display the owner of the item.

Information	Description
Group	Choose this option to display the group to which the item belongs.
Permissions	Choose this option to display the permissions of the item as three sets of three characters, for example <code>-rwxrwx-r--</code> .
Octal permissions	Choose this option to display the permissions of the item in octal notation, for example <code>764</code> .
MIME type	Choose this option to display the MIME type of the item.
None	Choose this option to display no information for the item.

To Set Preview Preferences

The file manager include some file preview features. The preview features can affect the speed with which the file manager responds to your requests. You can modify the behavior of some of these features to improve the speed of the file manager. For each preview preference, you can select one of the options described in the following table:

Option	Description
Always	Performs the action for both local files, and files on other file systems.
Local Files Only	Performs the action for local files only.
Never	Never performs the action.

To set your preview preferences, choose Edit → Preferences. Click on the **Preview** tab dialog to display the **Preview** tabbed section.

Table 7-9 lists the preview preferences that you can modify.

TABLE 7-9 Preview Preferences

Dialog Element	Description
Show text in icons	Select an option to specify when to preview the content of text files in the icon that represents the file.
Show thumbnails	Select an option to specify when to show thumbnails of image files. The file manager stores the thumbnail files for each folder in a <code>.thumbnails</code> directory that is one level below the folder.
Only for files smaller than	Specify the maximum file size for files for which the file manager creates a thumbnail.

TABLE 7-9 Preview Preferences (Continued)

Dialog Element	Description
Preview sound files	Select an option to specify when to preview sound files.
Count number of items	Select an option to specify when to show the number of items in folders. If you have set your View to Icon View, you might need to increase your default zoom level in the Views tabbed section to see the number of items in each folder.

Changing Backgrounds

The file manager includes backgrounds that you can use to change the look-and-feel of the following screen components:

- Desktop
- Side pane
- View pane
- Panels

To change the background of a screen component perform the following steps:

1. Choose Edit → Backgrounds and Emblems. The **Backgrounds and Emblems** dialog is displayed.
2. To display a list of patterns that you can use on the background, click on the Patterns button. To display a list of the colors that you can use on the background, click on the Colors button.
3. To change the background to a pattern, drag the pattern to the screen component. To change the background to a color, drag the color to the screen component.
4. Click Close to close the dialog.

To reset the background of the view pane or side pane to the default background, right-click on the background of the pane, then choose Use Default Background.

When you change the background of the side pane or the view pane of a particular folder, the file manager remembers the background that you chose. The next time that you display the folder, the background that you selected is displayed. In other words, when you change the background of a folder, you customize the folder to display the background.

To Add a Pattern

To add a pattern to the patterns that you can use on your screen components, choose Edit → Backgrounds and Emblems. Click on the Patterns button, then click on the Add a New Pattern button. A dialog is displayed. Use the dialog to find the new pattern. Click OK to add the new pattern to the **Backgrounds and Emblems** dialog.

To Add a Color

To add a color to the colors that you can use on your screen components, choose Edit → Backgrounds and Emblems. Click on the Colors button, then click on the Add a New Color button. A color selector dialog is displayed. Use the color wheel or the sliders to choose the color. Click OK to add the new color to the **Backgrounds and Emblems** dialog.

To Show and Hide Window Components

You can show and hide file manager window components as follows:

- To hide the side pane, choose View → Side Pane. To display the side pane again, choose View → Side Pane again.
- To hide the toolbar, choose View → Toolbar. To display the toolbar again, choose View → Toolbar again.
- To hide the location bar, choose View → Location Bar. To display the location bar again, choose View → Location Bar again.
- To hide the statusbar, choose View → Statusbar. To display the statusbar again, choose View → Statusbar again.
- To remove a tab from the side pane, right-click in the side pane. Choose the tab that you want to remove from the popup menu. To add the tab to the side pane again, choose the tab from the popup menu again.

Using Removable Media

The file manager supports all removable media that have the following characteristics:

- The removable media has an entry in the `/etc/fstab` file. The `/etc/fstab` file describes the file systems that the computer uses.
- The `user` option is specified in the entry for the removable media in the `/etc/fstab` file.

To Mount Media

To *mount* media is to make the file system of the media available for access. When you mount media, the file system of the media is attached as a subdirectory to your file system.

To mount media, insert the media in the appropriate device. An object that represents the media is added to the desktop. The object is added only if your system is configured to mount the device automatically when media is detected.

If your system is not configured to mount the device automatically, you must mount the device manually. Right-click on the desktop, then choose Disks → *device-name*. For example, to mount a floppy diskette, choose Disks → Floppy. An object that represents the media is added to the desktop.

Note – You cannot change the name of a removable media object.

To Display Media Contents

You can display media contents in any of the following ways:

- Double-click on the object that represents the media on the desktop.
- Right-click on the object that represents the media on the desktop, then choose Open.

A file manager window displays the contents of the media. To reload the display, click on the Reload button.

To Display Media Properties

To display the properties of removable media, right-click on the object that represents the media on the desktop, then choose Properties. A dialog displays the properties of the media.

To close the properties dialog, click Close.

To Format a Floppy Diskette

To *format* media is to prepare the media for use with a particular file system. You can use the file manager to format floppy diskettes.



Caution – When you format media, you overwrite any existing information on the media.

To format a floppy diskette, perform the following steps:

1. Insert the diskette in the diskette drive. Mount the diskette. For information on how to mount media, see “To Mount Media” on page 130.
2. Right-click on the object that represents the diskette on the desktop, then choose Format. A **Floppy formatter** dialog is displayed.
3. Select your format options in the **Floppy formatter** dialog. The following table describes the elements on the dialog:

Dialog Element	Description
Floppy device	Displays the name of the floppy device.
Floppy density	Select the density of the diskette. The density is the amount of data that the diskette can store.
File system type	Select the type of file system in which you want to format the diskette. Select one of the following options: <ul style="list-style-type: none"> ■ Linux Native (ext 2): Select this option to format a diskette for use on Linux systems. Most non-Linux systems cannot read diskettes with this file system type. ■ DOS (FAT): Select this option to format a diskette for use on Windows systems. Most UNIX-based systems can read diskettes with this file system type.
Volume name	Type a name for the diskette in this text box.
Quick	Select this option to create only the file system on the diskette. A quick format does not check for bad blocks. Select this option if the diskette has been formatted before.
Standard	Select this option to create the file system on the diskette and format the diskette. A standard format does not check for bad blocks. Select this option if the diskette has not been formatted before.
Thorough	Select this option to create the file system on the diskette, check for bad blocks, and format the diskette. Select this option if you want to verify that the diskette has not been damaged.

4. Click Format to format the diskette.

To Eject Media

To eject media, right-click on the media object on the desktop, then choose Eject. If the drive for the media is a motorized drive, the media is ejected from the drive. If the drive for the media is not motorized, wait until the desktop object for the media disappears, then eject the media manually.

You cannot eject media from a motorized drive when the media is mounted. To eject media, first unmount the media. To remove a floppy diskette from the drive, perform the following steps:

1. Close all file manager windows, Terminal windows, and any other windows that access the diskette.
2. Right-click on the object that represents the diskette on the desktop, then choose Eject. The desktop object for the diskette disappears.
3. Eject the diskette from the drive.



Caution – If you eject the diskette from the drive before you unmount the diskette, you might lose the data on the diskette.

Writing CDs

The file manager provides a special location where you can copy files and folders that you want to write to a CD. You can write the contents of the location to a CD easily.

To write a CD, perform the following steps:

1. Choose Go → CD Creator. The file manager opens a special location, **burn:///**, from which you can write CDs.
2. Copy the files and folders that you want to write to CD into the **burn:///** location.
3. Insert a writable CD into the CD writer device on your system.
4. Choose File → Write to CD. A **Write files to a CD recorder** dialog is displayed.
5. Use the **Write files to a CD recorder** dialog to specify how you want to write the CD, as follows:

Dialog Element	Description
Target to write to	Select the device to which you want to write the CD from the drop-down list. To create an CD image file for the files and folders, select the File image option.
Write speed	Select the speed at which you want to write the CD from the drop-down list.
CD name	Type a name for the CD in the text box.
Erase CD	Select this option to erase the current contents of the CD.
Eject CD when done	Select this option to eject the CD from the drive when the CD is written.
Reuse these files for another CD	Select this option if you do not want to write the files and folders to another CD. If you select this option, the files and folders are not removed from the burn:/// location after the CD is written.

- Click on the Write files to CD button.

If you selected the **File image** option from the **Target to write to** drop-down list, a **Choose a filename for the cdrom image** dialog is displayed. Use the dialog to specify the location where you want to save the CD image file. By default, CD image files have a `.iso` file extension.

A **Writing CD** dialog is displayed. When the CD is written or when the CD image file is created, a message to indicate that the process is complete is displayed in the dialog.

If you created a CD image file, you can write this file to a CD. To write a CD image file to CD, right-click on the CD image file, then choose Write to CD from the popup menu.

If you did not select the **Reuse these files for another CD** option, the files and folders are removed from the **burn:///** location.

Running Scripts From the File Manager

The file manager includes a special folder where you can store your scripts. When you add an executable file to this folder, the file is added to the Scripts submenu. To run a script choose File → Scripts, then choose the script that you want to run from the submenu.

To run a script on a particular file, select the file in the view pane. Choose File → Scripts, then choose the script that you want to run on the file from the submenu. You can also select multiple files to run your scripts on.

To view the contents of your scripts folder, choose File → Scripts → Open Scripts Folder.

Mounting and Unmounting a File System

To mount a file system is to make the file system available for access. When you mount a file system, the file system is attached as a subdirectory to your file system.

You can mount a directory on a remote system, or a file system on a device attached to a system that you can access. You must have `root` access permissions to mount or unmount a file system.

When you do not need to access the file system, you can unmount the file system.

To Mount a File System

To mount a file system, perform the following steps:

1. Right click on a folder in the file manager and choose Sharing → Mount. A **Mounting/Unmounting** dialog is displayed.

Note – If the Unmount menu item is in the popup menu, the directory that you selected already has a file system mounted.

2. Enter the information for the file system that you want to mount in the **Mounting/Unmounting** dialog. The following table describes the elements on the dialog:

Dialog Element	Description
mount local Directory	Displays the name of the currently selected folder.

Dialog Element	Description
as directory	Enter the path of the file system that you want to mount on the folder.
on remote machine	If the on remote machine is selected, this means that the file system to mount is on another system. You must enter the IP address or DNS name of the system.

- To select advanced options for the file system that you want to mount, click on the Advanced button. A **Mount Options** dialog is displayed. The following table describes the elements on the dialog:

Dialog Element	Description
Read Write	Select this option to assign read and write access permissions to the mounted file system.
Read Only	Select this option to assign read only access permissions to the mounted file system.
Specify mount type	Select this option to specify the type of file system to mount. Enter the file system type in the field.
Specify additional options: (comma separated)	Select this option to specify further options for the file system that you want to mount. Enter the options in the field. Use a comma to separate each option.

- Click on the Mount button. A dialog displays a success or failure message.

To Unmount a File System

To unmount a file system, perform the following steps:

- Right click on a folder in the file manager and choose Sharing → Unmount. A **Mounting/Unmounting** dialog is displayed with details of the mounted file.

Note – If the Mount menu item is in the popup menu, the directory that you selected does not have a file system mounted.

- Click on the Unmount button. A dialog displays a success or failure message.

Using NFS Shares

You can use Network File System (NFS) shares to make folders available to other systems. You must have `root` access permissions to add or remove NFS shares.

To Add an NFS Share

To add an NFS share to a folder, perform the following steps:

1. Right click on a folder in the file manager and choose Sharing → Add/Remove NFS Share. A **Share** dialog is displayed.
2. Enter the information for the folder that you want to share in the **Share** dialog. The following table describes the elements on the dialog:

Dialog Element	Description
Share to client(s)	Enter the name of the system or group of systems with which you want to share the folder.
Read Only	Select this option to assign read only access permissions to the folder.
Read Write	Select this option to assign read and write access permissions to the folder.

3. To configure advanced options for the share, click on Advanced. The **Advanced Sharing Properties** dialog is displayed. The following table describes the elements on the dialog:

Dialog Element	Description
Allow connections from port 1024 and higher	NFS shares that start on port numbers less than 1024 must start with <code>root</code> permissions. Select this option to enable users, other than <code>root</code> , to start NFS shares.
Allow asynchronous server reply	Select this option to enable the NFS server to reply to a request before any changes made by that request are saved. This option can cause data to be lost or corrupted if you start the NFS server after a system crash.

Dialog Element	Description
Allow asynchronous write	<p>Select this option if you do not want any delay when data is saved. This option has no effect if the Allow asynchronous server reply option is selected.</p> <p>If an NFS server receives small unrelated requests, deselect this option to increase performance.</p>
Allow transparent recursive mapping	<p>If a server exports two file systems, one of which is mounted on the other, then the client must mount both file systems.</p> <p>If the client mounts only the parent file system, the other file system is not displayed and contains an empty directory.</p> <p>Select this option if you want to display the file system. This allows an authorized client to transparently move from the parent file system to another file system.</p>
Enable subtree consistency checking	<p>Select this option to enable subtree checking. If a subdirectory of a file system is exported to another system, but the entire file system is not exported, the server checks if the requested file is contained in the exported subdirectory. This check is called subtree checking.</p> <p>If you want to export an entire file system, deselect this option to increase the transfer rate.</p>
Treat client root as server root	<p>Do not select this option unless it is absolutely necessary.</p> <p>By default, the user ID and group ID of the <code>root</code> user are both 0. Root permissions on the client are not mapped to root permissions on the NFS server.</p> <p>If this option is selected, root permissions are not mapped to an anonymous user, and <code>root</code> on a client has root permissions to export your directories.</p> <p>Note – If you select this option, you decrease the security of your system.</p>
Treat all clients' users as anonymous users	<p>Select this option to map all user IDs and group IDs to an anonymous user.</p>
Specify local ID for anonymous users:	<p>If the Treat all clients' users as anonymous users option is selected, this option enables you specify a user ID for an anonymous user.</p>
Specify local group ID for anonymous users:	<p>If the Treat all clients' users as anonymous users option is selected, this option enables you specify a group ID for an anonymous user.</p>

4. Click on the Add button. A dialog displays a success or failure message.

To Remove an NFS Share

To remove an NFS share from a folder, perform the following steps:

1. Right click on the folder in the file manager and choose Sharing → Add/Remove NFS Share. A **Share** dialog is displayed.
2. Click on the Remove button. A dialog displays a success or failure message.

Using Your Desktop

The Nautilus file manager manages the desktop. This chapter describes how to use the Nautilus desktop.

- “Introduction to the Desktop” on page 141
- “Desktop Objects” on page 142
- “Using Trash on the Desktop” on page 147
- “Using the Desktop Menu” on page 148
- “Changing the Pattern or Color of the Desktop” on page 149

Introduction to the Desktop

The desktop lies behind all of the other components on your visible desktop. The desktop is an active component of the user interface. You can perform the following tasks from your desktop:

- Start your applications, and open your files and folders.
You can add desktop objects for convenient access to files, folders, and applications that you use frequently. For example, you can add an application launcher to the desktop. You can create a symbolic link to a file that you use often, then add this link to your desktop. You can also store files and folders on the desktop.
- Open the Desktop menu.
Right-click on the desktop to open the Desktop menu. You can use the Desktop menu to perform actions on the desktop.
- Work with **Trash**.
You can move objects to **Trash** and empty your **Trash**.
- Customize your desktop.
You can customize the pattern or color of the desktop.

Desktop Objects

A desktop object is an icon on your desktop that you can use to open your files, folders, and applications. By default, your desktop contains three objects. You can also add objects to your desktop to provide convenient access to files, folders, applications, and URIs that you use frequently. For example, you can add a launcher to your desktop to enable you to open a particular application that you use often.

Table 8–1 describes the types of object that you can add to your desktop.

TABLE 8–1 Types of Desktop Objects

Object Type	Description
Symbolic link	<p>A symbolic link is an object that points to another file or folder. When you choose a symbolic link from the desktop, the file or folder that the symbolic link points to is opened. You can move or copy a symbolic link to the desktop.</p> <p>You can identify symbolic links by the default arrow emblem that appears on all symbolic links.</p>
Launcher	<p>You can add the following types of launcher to the desktop:</p> <ul style="list-style-type: none">■ Application: Starts a particular application.■ Link: Links to a particular file, folder, or URI.
File	<p>You can add files to your desktop. Files on your desktop reside in your desktop directory.</p>
Folder	<p>You can move folders to your desktop, and you can create folders on your desktop. Folders on your desktop reside in your desktop directory.</p>

The following sections describe how to work with objects on the desktop.

To Select Objects on the Desktop

To select an object on the desktop, click on the object. To select multiple objects, press-and-hold Ctrl, then click on the objects that you want to select.

You can also select an area on the desktop to select all objects within that area. Click-and-hold on the desktop, then drag over the area that contains the objects that you want to select. When you click-and-hold then drag, a rectangle appears to mark the area that you select.

To select multiple areas, press-and-hold Ctrl, then drag over the areas that you want to select.

To Open an Object from the Desktop

To open an object from the desktop, double-click on the object. Alternatively, right-click on the object, then choose Open. When you open an object, the default action for the object executes. For example, if the object is a text file, the text file opens in a file manager window. The default actions for file types are specified in the File Associations preference tool.

To execute an action other than the default action for an object, right-click on the object, then choose Open With. Choose an action from the Open With submenu.

The items in the Open With submenu correspond to the contents of the following parts of the File Associations preference tool:

- **Default action** drop-down list in the **Edit file type** dialog
- **Viewer Component** drop-down list in the **Edit file type** dialog

You can set your preferences in a file manager window so that you click once on a file to execute the default action.

To Add a Launcher to the Desktop

A desktop launcher can start an application or link to a particular file, folder, FTP site, or URI location.

To add a launcher to your desktop, perform the following steps:

1. Right-click on the desktop, then choose New Launcher. A **Create Launcher** dialog is displayed.
2. For information on how to enter the properties of the launcher in the **Create Launcher** dialog, see *Working With Panels*. The command that you enter for the launcher is the command that is executed when you use the desktop object.

To Add a Symbolic Link to the Desktop

You can create symbolic links on your desktop to perform the following actions:

- Open a particular file in a particular application.
- Open a particular folder in a file manager window.
- Run a binary file or a script.

To create a symbolic link on the desktop, perform the following steps:

1. Display the file or folder for which you want to create a symbolic link in a file manager window.
2. Create a symbolic link to the file or folder. To create a symbolic link to a file or folder, select the file or folder to which you want to create a link. Choose Edit → Make Link. A link to the file or folder is added to the current folder. You can

identify symbolic links by the default arrow emblem that appears on all symbolic links. The following figure shows a symbolic link to a file:



3. Drag the symbolic link to the desktop. The icon for the object is moved to the desktop.

Adding a File or Folder to the Desktop

The following sections describe how you can add file objects and folder objects to the desktop.

To Move a File or Folder to the Desktop

You can move a file or folder from the file manager to the desktop. To move a file or folder to the desktop, perform the following steps:

1. Open a file manager window.
2. In the view pane, display the file or folder that you want to move.
3. Drag the file or folder to the desktop. The icon for the file or folder is moved to the desktop. The file or folder is moved to your desktop directory.

Alternatively, select the file or folder, then choose Edit → Cut Files. Right-click on any desktop object, then choose Paste Files.

To Copy a File or Folder to the Desktop

You can copy a file or folder from the file manager to the desktop. To copy a file or folder to the desktop, perform the following steps:

1. Open a file manager window.
2. In the view pane, display the file or folder that you want to move.
3. Press-and-hold Ctrl, then drag the file or folder to the desktop. An icon for the file or folder is added to the desktop. The file or folder is copied to your desktop directory.

Alternatively, select the file or folder, then choose Edit → Copy Files. Right-click on any desktop object, then choose Paste Files.

To Create a Folder Object on the Desktop

To create a folder object, right-click on the desktop to open the Desktop menu. Choose New Folder. An **untitled** folder is added to the desktop. Type the name of the new folder, then press Return. The folder is displayed with the new name. The new folder resides in your desktop directory.

To Rename a Desktop Object

To rename a desktop object, right-click on the object, then choose Rename. The name of the desktop object is highlighted. Type the new name for the object, then press Return.

To Remove an Object from the Desktop

To remove an object from the desktop, right-click on the object, then choose Move to Trash. Alternatively, drag the object to **Trash**.

Note – When you move a file or folder from a removable media to **Trash**, the file or folder is stored in a **Trash** location on the removable media. To remove the file or folder permanently from the removable media, you must empty **Trash**.

To Delete an Object from the Desktop

When you delete an object from the desktop, the object is not moved to **Trash**, but is immediately deleted from the desktop. The Delete menu item is only available if you select the **Include a Delete command that bypasses Trash** option in the Nautilus **File Management Preferences** dialog.

To delete an object from the desktop right-click on the object, then choose Delete.

Note – You cannot delete the **Home** or **Trash** desktop objects.

To View the Properties of a Desktop Object

To view the properties of a desktop object, perform the following steps:

1. Right-click on the object whose properties you want to view, then choose Properties. A properties dialog is displayed.

2. Use the properties dialog to view the properties of the desktop object.
3. Click Close to close the properties dialog.

To Change the Permissions of a Desktop Object

To change the permissions of a desktop object, perform the following steps:

1. Right-click on the object whose permissions you want to change, then choose Properties. A properties dialog is displayed.
2. Click on the **Permissions** tab to display the **Permissions** tabbed section.
3. In the **Permissions** tabbed section, use the drop-down lists and check boxes to change the permissions for the file or folder. For more information on the dialog elements in the **Permissions** tabbed section, see *Nautilus File Manager*.
4. Click Close to close the properties dialog.

To Add an Emblem to a Desktop Object

To add an emblem to a desktop object, perform the following steps:

1. Right-click on the object to which you want to add an emblem, then choose Properties. A properties dialog is displayed.
2. Click on the **Emblems** tab to display the **Emblems** tabbed section.
3. Select the emblem to add to the item.
4. Click Close to close the properties dialog.

To Add a Note to a Desktop Object

To add a note to a desktop object, perform the following steps:

1. Select the object to which you want to add a note.
2. Choose File → Properties. A properties dialog is displayed.
3. Click on the **Notes** tab. In the **Notes** tabbed section, type the note.
4. Click Close to close the properties dialog. A note emblem is added to the desktop object.

To delete a note, delete the note text from the **Notes** tabbed section.

To Change the Icon for a Desktop Object

To change the icon for desktop object, perform the following steps:

1. Right-click on the object whose permissions you want to change, then choose Properties. A properties dialog is displayed.
2. On the **Basic** tabbed section, click on the Select Custom Icon button. A **Select an icon** dialog is displayed.
3. Use the **Select an icon** dialog to choose the icon to represent the file or folder.
4. Click Close to close the properties dialog.

To restore an icon from a custom icon to the default icon specified in the File Types and Programs preference tool, right-click on the icon then choose Remove Custom Icon. Alternatively, click on the **Remove Custom Icon** button on the **Properties** dialog.

To Resize a Desktop Object Icon

You can change the size of the icon that represents a desktop object. To change the size of an icon on the desktop, perform the following steps:

1. Right-click on the desktop object whose icon you want to resize, then choose Stretch Icon. A rectangle appears around the icon, with a handle at each corner.
2. Grab one of the handles, then drag the icon to the size that you want.

To return the icon to the original size, right-click on the icon, then choose Restore Icon's Original Size.

Using Trash on the Desktop

You can move the following items to **Trash**:

- Files
- Folders
- Desktop objects

If you need to retrieve a file from **Trash**, you can view **Trash** and move the file out of **Trash**. When you empty **Trash**, you delete the items in **Trash** permanently.

To Display Trash

You can display the contents of **Trash** in the following ways:

- From the desktop
Double-click on the **Trash** object on the desktop. The contents of **Trash** are displayed in a Nautilus window.


- From a file manager window
Choose Go → Trash. The contents of **Trash** are displayed in the window.

To Empty Trash

You can empty the contents of **Trash** in the following ways:

- From the desktop
Right-click on the **Trash** object, then choose Empty Trash.
- From a file manager window
Choose File → Empty Trash.

Using the Desktop Menu



To open the Desktop menu, right-click on a vacant space on the desktop. You can use the Desktop menu to perform actions on the desktop.

Table 8–2 describes the items in the Desktop menu.

TABLE 8–2 Items on the Desktop Menu

Menu Item	Function
New Window	Opens a new file manager window that displays your home location.

TABLE 8–2 Items on the Desktop Menu (Continued)

Menu Item	Function
New Folder	Creates a new folder object on your desktop. The folder is created in your desktop directory.
New Terminal	Starts a GNOME Terminal.
New Launcher	Creates a launcher on your desktop. For more information, see “To Add a Launcher to the Desktop” on page 143.
Scripts	Opens a submenu of scripts that you can run.
Clean Up By Name	Arranges the objects on the desktop alphabetically by name.
Keep Aligned	Ensures that the left edges of the objects on the desktop are aligned with one another.
Cut Files	Deletes the selected file or files from the folder or desktop, and places the file or files in buffer.
Copy Files	Copies the selected file or files from the folder or desktop, and places the file or files in buffer.
Paste Files	Puts the file or files in the buffer into the selected folder or the desktop.
Disks	Enables you to mount diskettes and other removable media.
Use Default Background	Resets the desktop background to the last pattern that you chose from the Backgrounds and Emblems dialog. You can access the Backgrounds and Emblems dialog from Nautilus windows.
Change Desktop Background	Starts the Background preference tool to enable you to change the desktop background.

Changing the Pattern or Color of the Desktop

You can change the pattern or color of the desktop background to suit your preferences. The file manager includes background patterns and colors that you can use to change the look-and-feel of the desktop background.

You can change the pattern or color of the desktop background in any of the following ways:

- Drag a pattern or color from another window or dialog to the desktop.

If your desktop background is a color, you can create a gradient effect from a color into the desktop background color. A gradient effect is a visual effect where one color blends gradually into another color. To create a gradient effect on your desktop background, drag a color to one of the edges of the screen. The color blends from the edge to which you drag the color, to the opposite edge of the screen.

Before you drag a color to a screen edge, check if there is an edge panel on the screen edge. If there is an edge panel on the screen edge, you must hide the panel before you drag the color.

- Use the Background preference tool.
- Choose a pattern or color for the background from the **Backgrounds and Emblems** dialog. To change the pattern or color of the desktop background, perform the following steps:
 1. Open a file manager window.
 2. Choose Edit → Backgrounds and Emblems. The **Backgrounds and Emblems** dialog is displayed.
 3. To display a list of patterns that you can use, click on the Patterns button. To display a list of the colors that you can use, click on the Colors button.
 4. To change the desktop background to a pattern, drag the pattern to the desktop background. To change the desktop background to a color, drag the color to the desktop background.
 5. Click Close to close the dialog.

Customizing Your GNOME Desktop

You can customize many of the characteristics of the GNOME Desktop. The customization of each aspect of the GNOME Desktop is controlled by a dedicated software tool that is called a preference tool. This section describes how to configure the GNOME Desktop in the following chapters.

- *Starting Preference Tools*

Read this chapter to find out how to start the preference tools in the GNOME Desktop.

- *Using Preference Tools*

Read this chapter to find out how to use the preference tools to customize the GNOME Desktop. This chapter describes all the options in each of the preference tools.

Starting Preference Tools

This chapter describes how to start your preference tools, and where to find the preference tools in the GNOME Desktop menu structure.

- “Starting a Preference Tool” on page 153
- “Where to Find Preference Tools” on page 153

Starting a Preference Tool

You can start the preference tools in the following ways:

- Choose Preferences from the Main Menu. Choose the tool that you require from the submenus.
- Double-click on the **This Computer** object on the desktop. A file manager window opens at the **This Computer** location. Double-click on the **Preferences** object in the file manager window to display your preference tools. Double-click on the tool that you require.

Where to Find Preference Tools

Table 9–1 lists the preference tools in the GNOME Desktop, and where you can find each preference tool in the menu structure.

TABLE 9-1 Location of Preference Tools in GNOME Desktop Menu Structure

Preference Tool	Menu Path
Background Preferences	Preferences → Display → Background
CD Database	Preferences → Advanced → CD Database Server
CD Device Options	Preferences → Advanced → CD Device Options
File Associations	Preferences → Advanced → File Associations
Folder Options	Preferences → Folders
Font	Preferences → Display → Font
Internet	Preferences → Internet
Java	Preferences → Java
Keyboard Accessibility	Preferences → Keyboard → Accessibility
Keyboard Behavior	Preferences → Keyboard → Behavior
Keyboard Layout	Preferences → Keyboard → Layout
Menus and Toolbars	Preferences → Display → Menus & Toolbars
Mouse	Preferences → Mouse
Multimedia Keys	Preferences → Keyboard → Multimedia Keys
Panel Preferences	Preferences → Advanced → Panel
Password	Preferences → Password
PDA Devices	Preferences → PDA Devices
Preferred Applications	Preferences → Advanced → Preferred Applications
Printers	Preferences → Printers
Remote Desktop Preferences	Preferences → Remote Desktop
Screen Resolution Preferences	Preferences → Display → Screen Resolution
Screensaver Preferences	Preferences → Display → Screensaver
Sessions	Preferences → Advanced → Sessions
Shortcuts	Preferences → Keyboard → Shortcuts
Sound Preferences	Preferences → Sound
System	Preferences → System
Theme	Preferences → Display → Theme

TABLE 9-1 Location of Preference Tools in GNOME Desktop Menu Structure *(Continued)*

Preference Tool	Menu Path
Windows	Preferences → Display → Window Behavior

Using Preference Tools

This chapter describes how to use the preference tools to customize the GNOME Desktop.

- “Customizing the Desktop Background” on page 158
- “Configuring a CD Database” on page 159
- “Customizing CD Device Options” on page 160
- “Configuring File Associations” on page 161
- “Setting File Management Preferences” on page 164
- “Choosing Default Fonts” on page 164
- “Configuring Your Internet Connection” on page 166
- “Configuring Keyboard Accessibility Options” on page 167
- “Configuring Keyboard Preferences” on page 170
- “Configuring Keyboard Layout” on page 171
- “Customizing Menus and Toolbars in Applications” on page 172
- “Setting Mouse Preferences” on page 172
- “Configuring Multimedia Keys” on page 174
- “Customizing Your Panels” on page 175
- “Changing Your Password” on page 175
- “Choosing Your Preferred Applications” on page 175
- “Setting Screen Resolution Preferences” on page 177
- “Setting Screensaver Preferences” on page 178
- “Configuring Sessions” on page 181
- “Customizing Keyboard Shortcuts” on page 184
- “Configuring Printers” on page 185
- “Setting Session Sharing Preferences” on page 185
- “Setting Sound Preferences” on page 186
- “Customizing Themes” on page 188
- “Customizing Windows” on page 190

Customizing the Desktop Background

The desktop background is the image or color that is applied to your desktop. You can customize the desktop background in the following ways:

- Select an image for the desktop background. The image is superimposed on the desktop background color. The desktop background color is visible if you select a transparent image, or if the image does not cover the entire desktop.
- Select a color for the desktop background. You can select a solid color, or create a gradient effect with two colors. A gradient effect is a visual effect where one color blends gradually into another color.

You can also change the appearance of your desktop background from within the Nautilus file manager.

Table 10–1 lists the background preferences that you can modify.

TABLE 10–1 Desktop Background Preferences

Dialog Element	Description
Select picture	Choose an image to display on the desktop. To choose an image, click on the Select picture button. An image selector dialog is displayed. Use the dialog to choose an image. When you choose an image, click OK.
Picture Options	To specify how to display the image, select one of the following options: <ul style="list-style-type: none">■ Wallpaper: Repeats the image to cover the desktop.■ Centered: Displays the image in the middle of the desktop.■ Scaled: Enlarges the image until the image meets the screen edges, and maintains the relative dimensions of the image.■ Stretched: Enlarges the image to cover the desktop, and does not maintain the relative dimensions of the image.■ No Picture: Displays no image.

TABLE 10-1 Desktop Background Preferences (Continued)

Dialog Element	Description
Background Style	<p>To specify a color scheme, use the options in the Background Style drop-down list, and the color selector buttons.</p> <p>You can specify a color scheme in one of the following ways:</p> <ul style="list-style-type: none">■ Choose Solid color from the Background Style drop-down list to specify a single color for the desktop background. To choose the color that you require, click on the Color button. The Pick a Color dialog is displayed. Choose a color, then click OK.■ Choose Horizontal gradient from the Background Style drop-down list. This option creates a gradient effect from the left screen edge to the right screen edge. Click on the Left Color button to display the Pick a Color dialog. Choose the color that you want to appear at the left edge. Click on the Right Color button. Choose the color that you want to appear at the right edge.■ Choose Vertical gradient from the Background Style drop-down list. This creates a gradient effect from the top screen edge to the bottom screen edge. Click on the Top Color button to display the Pick a Color dialog. Choose the color that you want to appear at the top edge. Click on the Bottom Color button. Choose the color that you want to appear at the bottom edge.

Configuring a CD Database

The CD Database preference tool enables you to configure a CD database that your system can query. A CD database contains information about CDs, such as the name of the artist, the title, and the track list. When an application plays a CD, the application can query the CD database about the CD, then display the information.

Table 10-2 describes the preferences in the CD Database preference tool.

TABLE 10-2 CD Database Preferences

Dialog Element	Description
Send no info	Select this option if you do not want to send any information to the CD database server.

TABLE 10–2 CD Database Preferences *(Continued)*

Dialog Element	Description
Send real info	Select this option to send your name and hostname information to the CD database server.
Send other info	Select this option to send another name and hostname to the CD database server. Enter the name in the Name field. Enter the hostname in the Hostname field.
FreeDB round robin server	FreeDB is a CD database. The FreeDB round robin server is a load-sharing configuration of FreeDB servers. Select this option to access the FreeDB CD database from this server.
Other FreeDB server	Select this option to access the FreeDB CD database from another server. Select the server that you require from the server table.
Update server list	Click on this button to update the list of available FreeDB servers in the server table.
Other server	Select this option to use another CD database. Enter the name of the server on which the database resides in the Hostname field. Enter the port number on which you can access the database in the Port field.

Customizing CD Device Options

The CD Device Options preference tool enables you to configure options for CD devices on your system. The **CD Device Options** dialog enables you to configure options for the following:

- Data CDs
- Audio CDs
- Blank CDs
- DVDs (Videos)

Table 10–3 describes the preferences in the CD Device Options preference tool.

TABLE 10–3 CD Device Preferences

Dialog Element	Description
Mount CD when inserted	Select this option to mount the file system of a CD.
Start auto-run program on newly mounted CD	Select this option to automatically start the auto-run program on a newly-mounted data CD.

TABLE 10-3 CD Device Preferences (Continued)

Dialog Element	Description
Open the file manager for newly mounted CD	Select this option to open the file manager for a newly-mounted data CD.
Run command when CD is inserted	Select this option to run a command when you insert a CD. Enter the command to run when you insert the CD in the Command field. Alternatively, to choose a command that you entered previously, click the down arrow button, then choose the command to run. You can also use the Browse button to choose a command to run.
Run command when blank CD is inserted	Select this option to run a command when you insert a blank CD. Enter the command to run when you insert the blank CD in the Command field.
Run command when DVD (video) is inserted	Select this option to run a command when you insert a DVD. Enter the command to run when you insert the DVD in the Command field.

Configuring File Associations

Use the File Associations preference tool to configure the following:

File types You can specify how files of various types are displayed and edited. For example, you can specify an icon to represent a particular type of file. For another example, you can specify that if a file is a plain text file, the file is launched in a text editor.

The file manager and other GNOME applications check the contents of a file to determine the type of a file. If the first lines do not determine the type of the file, then the application checks the filename.

Services A *Uniform Resource Identifier* (URI) is a string that identifies a particular location in a file system or on the Web. For example, the web address of a web page is a URI. A *service* is a protocol or task that a URI requests. For example, the `http://www.gnome.org` URI requests the `http` service.

You can associate an application with a service, so that the application performs the task required by the service. For example, you can associate your preferred web browser with the `http` service.

Table 10–4 describes the elements on the File Associations preference tool.

TABLE 10–4 Elements on File Associations Preference Tool

Element	Description
Table	To view the contents of a category of file types, click on the right arrow next to the category name. The category expands, and displays a description of each file type, and the file extension that is associated with the file type. To select a file type that you want to work with, click on the file type.
Add File Type	Click on this button to add a file type. For more information, see “To Add a File Type” on page 162.
Add Service	Click on this button to add a service. For more information, see “To Add a Service” on page 163.
Edit	To edit a file type, a service, or a file type category, select the item that you want to edit, then click Edit.
Remove	To delete a file type or a service, select the item that you want to delete, then click Remove.

To Add a File Type

To add a file type, perform the following steps:

1. Start the File Associations preference tool.
2. Click on the Add File Type button. The **Add File Type** dialog is displayed.
3. Enter the properties of the file type in the dialog. The following table describes the dialog elements on the **Add File Type** dialog:

Dialog Element	Description
No Icon	Choose an icon to represent the file type. To choose an icon, click on the No Icon button. An icon selector dialog is displayed. Choose an icon from the dialog. Alternatively, to choose an icon from another directory, click Browse. When you choose an icon, click OK.
Description	Type a description of the file type.
MIME type	Enter the MIME type for this type of file.

Dialog Element	Description
Category	Enter the category to which you want the file type to belong in this preference tool. Click on the Choose to choose a category from the Choose a file category dialog.
Filename extensions	Enter the file extensions to associate with the file type. Enter a file extension in the field on the left side, then press Return. To delete a file extension, select the file extension in the field on the right side, then click on the Remove button.
Viewer Component	Select the viewer component to use to display files of this type in the file manager.
Default action	Select the default application to use to open files of this type.
Program to run	Specify a program to associate with the file type. Enter the command to start the program in this field. Alternatively, to choose a command that you entered previously, click the down arrow button, then choose the command to run. You can also use the Browse button to choose a command to run.
Run in Terminal	Select this option to run the program in a terminal window. Choose this option for a program that does not create a window in which to run.

4. Click OK.

To Add a Service

To add a service, perform the following steps:

1. Start the File Associations preference tool.
2. Click on the Add Service button. The **Add Service** dialog is displayed.
3. Enter the properties of the service in the dialog. The following table describes the dialog elements on the **Add Service** dialog:

Dialog Element	Description
Description	Type a description of the service.
Protocol	Enter the protocol for the service.

Dialog Element	Description
Program to Run	Information to be supplied in a future release.
Program	Specify the program to associate with the service. Enter the command to start the program in this field. Alternatively, to choose a command that you entered previously, click the down arrow button, then choose the command to run. You can also use the Browse button to choose a command to run.
Run in Terminal	Select this option to run the program in a terminal window. Choose this option for a program that does not create a window in which to run.

4. Click OK.

Setting File Management Preferences

Use the Folder Options preference tool to set your Nautilus file manager preferences. You can also set your file manager preferences in the **Folder Options** preferences dialog, which you can open from the file manager application. For information on the preferences in the **Folder Options** preferences dialog and Folder Options preference tool, see *Nautilus File Manager*.

Choosing Default Fonts

Use the Font preference tool to select the fonts to use in your applications, windows, terminals, and desktop.

Table 10–5 lists the font preferences that you can modify.

TABLE 10–5 Font Preferences

Dialog Element	Description
Application font	Click on the font selector button to select a font to use in your applications.

TABLE 10–5 Font Preferences (Continued)

Dialog Element	Description
Desktop font	Click on the font selector button to select a font to use on your desktop only.
Window title font	Click on the font selector button to select a font to use in the titlebars of your windows.
Terminal font	Click on the font selector button to select a font to use in the Terminal application
Font Rendering	<p>To specify how to render fonts on your screen, select one of the following options:</p> <ul style="list-style-type: none"> ■ Monochrome: Renders fonts in black and white only. The edges of characters might appear jagged in some cases because the characters are not antialiased. <i>Antialiasing</i> is an effect that is applied to the edges of characters to make the characters look smoother. ■ Best shapes: Antialiases fonts where possible. Use this option for standard Cathode Ray Tube (CRT) monitors. ■ Best contrast: Adjusts fonts to give the sharpest possible contrast, and also antialiases fonts, so that characters have smooth edges. This option might enhance the accessibility of the GNOME Desktop to users with visual impairments. ■ Subpixel smoothing (LCDs): Uses techniques that exploit the shape of individual Liquid Crystal Display (LCD) pixels to render fonts smoothly. Use this option for LCD or flat-screen displays.
Details	<p>Click on this button to specify further details of how to render fonts on your screen.</p> <ul style="list-style-type: none"> ■ Resolution (dots per inch): Use the spin box to specify the resolution to use when your screen renders fonts. ■ Smoothing: Select one of the options to specify how to antialias fonts. ■ Hinting: <i>Hinting</i> is a font-rendering technique that improves the quality of fonts at small sizes and an at low screen resolutions. Select one of the options to specify how to apply hinting your fonts. ■ Subpixel order: Select one of the options to specify the subpixel color order for your fonts. Use this option for LCD or flat-screen displays.

Previewing Fonts

You can use the file manager to preview fonts. To preview fonts, perform the following steps:

1. Open a file manager window.
2. Enter the URI `font s:///` in the location bar. The fonts are displayed as icons in the view pane.
3. Double-click on an icon to display a preview of the font.

Configuring Your Internet Connection

The Internet preference tool enables you to configure how your system connects to the Internet. You can configure the GNOME Desktop to connect to a *proxy server*, and specify the details of the proxy server. A proxy server is a server that intercepts requests to another server, and fulfills the request itself, if it can. You can enter the Domain Name Service (DNS) name or the Internet Protocol (IP) address of the proxy server. A *DNS name* is a unique alphabetic identifier for a computer on a network. An *IP address* is a unique numeric identifier for a computer on a network.

Table 10–6 lists the Internet connection preferences that you can modify.

TABLE 10–6 Internet Connection Preferences

Dialog Element	Description
Direct internet connection	Select this option if you want to connect directly to the Internet, without a proxy server.
Manual proxy configuration	Select this option if you want to connect to the Internet through a proxy server, and you want to configure the proxy server manually.
HTTP proxy	Enter the DNS name, or the IP address of the proxy server to use when you request a HTTP service. Enter the port number of the HTTP service on the proxy server in the Port spin box.
Secure HTTP proxy	Enter the DNS name, or the IP address of the proxy server to use when you request a Secure HTTP service. Enter the port number of the Secure HTTP service on the proxy server in the Port spin box.
FTP proxy	Enter the DNS name, or the IP address of the proxy server to use when you request a FTP service. Enter the port number of the FTP service on the proxy server in the Port spin box.
Socks host	Enter the DNS name, or the IP address of the Socks host to use. Enter the port number for the Socks protocol on the proxy server in the Port spin box.

TABLE 10-6 Internet Connection Preferences *(Continued)*

Dialog Element	Description
Automatic proxy configuration	Select this option if you want to connect to the Internet through a proxy server, and you want to configure the proxy server automatically.
Autoconfiguration URL	Enter the URL that contains the information required to configure the proxy server automatically.

Configuring Keyboard Accessibility Options

Use the Keyboard accessibility preference tool to set the keyboard accessibility preferences. The Keyboard accessibility preference tool is also known as AccessX.

You can customize the preferences for the keyboard accessibility in the following functional areas:

- **Basic**
- **Filters**
- **Mouse**

Basic Preferences

Table 10-7 lists the basic keyboard accessibility preferences that you can modify.

TABLE 10-7 Keyboard Accessibility Preferences

Dialog Element	Description
Enable keyboard accessibility features	Select this option to enable keyboard accessibility features. When you select this option, the other options in the preference tool become available.

TABLE 10–7 Keyboard Accessibility Preferences (Continued)

Dialog Element	Description
Disable if unused for	Select this option to deactivate keyboard accessibility preferences if the keyboard is not used for a specified period of time. Use the slider to specify the number of seconds of keyboard idle time required before the system disables the keyboard accessibility preferences. When the specified number of seconds elapses, the following keyboard accessibility preferences are disabled: <ul style="list-style-type: none">■ Bounce keys■ Mouse keys■ Slow keys■ Sticky keys■ Toggle keys
Beep when features turned on or off from keyboard	Select this option for an audible indication when a feature such as sticky keys or slow keys is activated, or deactivated.
Import Feature Settings	Click on this button to import an AccessX configuration file.
Enable Sticky Keys	Select this option to perform multiple simultaneous keypress operations by pressing the keys in sequence. Alternatively, to enable the sticky keys feature, press Shift five times. You can set the following sticky keys preferences: <ul style="list-style-type: none">■ Beep when modifier is pressed: Select this option for an audible indication when you press a modifier key.■ Disable if two keys pressed together: Select this option to specify that when you press two keys simultaneously, you can no longer press keys in sequence to perform multiple simultaneous keypresses.
Repeat Keys	Select this option to enable the autorepeat settings for your keyboard. You can set the following autorepeat preferences: <ul style="list-style-type: none">■ Delay: Use the slider or the spin box to specify the interval to wait after the first keypress before the automatic repeat of a pressed key.■ Speed: Use the slider or the spin box to specify the number of characters per second to enter.
Type to test settings	The test area is an interactive interface so you can see how the keyboard settings affect the display as you type. Type text in the test area to test the effect of your settings.

For more information on configuring keyboard accessibility preferences, see *GNOME 2.2 Desktop Accessibility Guide*.

Filter Preferences

Table 10–8 lists the filter preferences that you can modify.

TABLE 10–8 Filter Preferences

Dialog Element	Description
Enable keyboard accessibility features	Select this option to enable keyboard accessibility features. When you select this option, the other options in the preference tool become available.
Enable Slow Keys	Select this option to control the period of time that you must press-and-hold a key before acceptance. Alternatively, to enable the slow keys feature, press-and-hold Shift for eight seconds. You can set the following slow keys preferences: <ul style="list-style-type: none">■ Only accept keys held for: Use the slider or the spin box to specify the period of time that you must press-and-hold a key before acceptance.■ Beep when key is: Select the appropriate option or options for an audible indication when a key is pressed, accepted, or rejected.
Enable Bounce Keys	Select this option to accept a key input and to control the key repeat characteristics of the keyboard. You can set the following bounce keys preferences: <ul style="list-style-type: none">■ Ignore duplicate keypresses within: Use the slider or the spin box to specify the interval to wait after the first keypress before the automatic repeat of a pressed key.■ Beep if key is rejected: Select this option for an audible indication of key rejection.
Enable Toggle Keys	Select this option for an audible indication of a toggle keypress. You hear one beep when a toggle key is turned on. You hear two beeps when a toggle key is turned off.
Type to test settings	The test area is an interactive interface so you can see how the keyboard settings affect the display as you type. Type text in the test area to test the effect of your settings.

For more information on configuring keyboard accessibility preferences, see *GNOME 2.2 Desktop Accessibility Guide*.

Mouse Preferences

Table 10–9 lists the mouse preferences that you can modify.

TABLE 10–9 Mouse Preferences

Dialog Element	Description
Enable keyboard accessibility features	Select this option to enable keyboard accessibility features. When you select this option, the other options in the preference tool become available.
Enable Mouse Keys	Select this option to make the numeric keypad emulate mouse actions. You can set the following mouse key preferences: <ul style="list-style-type: none"> ■ Maximum pointer speed: Use the slider or the spin box to specify the maximum speed that the pointer moves across the screen. ■ Time to accelerate to maximum speed: Use the slider or the spin box to specify the duration of the acceleration time of the pointer. ■ Delay between keypress and pointer movement: Use the slider or the spin box to specify the period of time that must pass after a keypress before the pointer moves.
Mouse Preferences	Click on this button to open the Mouse preference tool.

For more information on configuring keyboard accessibility preferences, see *GNOME 2.2 Desktop Accessibility Guide*.

Configuring Keyboard Preferences

Use the Keyboard Behavior preference tool to modify the autorepeat preferences for your keyboard, and to modify the sound preferences for your keyboard.

You can set the preferences for the Keyboard preference tool in the following functional areas:

- **Keyboard**
- **Sound**

Keyboard Preferences

Use the **Keyboard** tabbed section to set general keyboard preferences. To start the Keyboard *accessibility* preference tool, that is, AccessX, click on the Accessibility button.

Table 10–10 lists the keyboard preferences that you can modify.

TABLE 10–10 Keyboard Preferences

Dialog Element	Description
Keyboard repeats when key is held down	Select this option to enable keyboard repeat. If keyboard repeat is enabled, when you press-and-hold a key, the action associated with the key is performed repeatedly. For example, if you press-and-hold a character key, the character is typed repeatedly.
Delay	Select the delay from the time you press a key to the time that the action repeats.
Speed	Select the speed at which the action is repeated.
Blinks in text boxes and fields	Select this option to enable the cursor to blink in fields and text boxes.
Speed	Use the slider to specify the speed at which the cursor blinks in fields and text boxes.

Sound Preferences

Use the **Sound** tabbed section to set your preferences for keyboard sound.

Some applications play a bell sound to indicate a keyboard input error. Use the options in the **Sound** tabbed section to configure the bell sound. Table 10–11 lists the keyboard sound preferences that you can modify.

TABLE 10–11 System Bell Preferences

Dialog Element	Description
Off	Select this option to disable the keyboard bell.
Beep	Select this option to enable the keyboard bell.

Configuring Keyboard Layout

Use the Keyboard Layout preference tool to select a layout for your keyboard. You can choose different layouts to suit different locales. For more information on the Keyboard Layout preference tool, see the *Keyboard Layout Switcher* manual.

Customizing Menus and Toolbars in Applications

You can use the Menus & Toolbars preference tool to customize the appearance of menus, menubars, and toolbars for GNOME-compliant applications.

Table 10–12 lists the menu and toolbar preferences that you can modify for GNOME-compliant applications.

TABLE 10–12 Menu and Toolbar Preferences

Dialog Element	Description
Button Labels	Choose one of the following options to specify what to display on the toolbars in your GNOME-compliant applications: <ul style="list-style-type: none">■ Text Below Icons: Select this option to display toolbars with text as well as an icon on each button.■ Text Beside Icons: Select this option to display toolbars with an icon only on each button, and with text on the most important buttons.■ Icons Only: Select this option to display toolbars with an icon only on each button.■ Text Only: Select this option to display toolbars with text only on each button.
Toolbars can be detached and moved around	Select this option if you want to move toolbars from application windows to any location on the screen. If you select this option, handles are displayed on the left side of the toolbars in your applications. To move a toolbar, click-and-hold on the handle, then drag the toolbar to the new location.
Show icons in menus	Select this option to display an icon beside each item in a menu. Some menu items do not have an icon.

Setting Mouse Preferences

Use the Mouse preference tool to configure your mouse for right-hand use or for left-hand use. You can also specify the speed and sensitivity of mouse movement.

You can customize the settings for the Mouse preference tool in the following functional areas:

- **Buttons**

- **Cursors**
- **Motion**

Buttons Preferences

Use the **Buttons** tabbed section to specify whether the mouse buttons are configured for left-hand use. You can also specify the delay between clicks for a double-click.

Table 10–13 lists the mouse button preferences that you can modify.

TABLE 10–13 Mouse Button Preferences

Dialog Element	Description
Left-handed mouse	Select this option to configure your mouse for left-hand use. When you configure your mouse for left-hand use, the functions of the left mouse button and the right mouse button are swapped.
Timeout	Use the slider to specify the amount of time that can pass between clicks when you double-click. If the interval between the first and second clicks exceeds the time that is specified here, the action is not interpreted as a double-click.

Pointer Preferences

Use the **Cursors** tabbed section to set your mouse pointer preferences.

Table 10–14 lists the mouse pointer preferences that you can modify:

TABLE 10–14 Mouse Pointer Preferences

Dialog Element	Description
Small	Select this option to display a small mouse pointer.
Medium	Select this option to display a medium mouse pointer.
Large	Select this option to display a large mouse pointer.
Highlight the pointer when you press Ctrl	Select this option to enable a mouse pointer animation when you press and release Ctrl. This feature can assist you to locate the mouse pointer.

Motion Preferences

Use the **Motion** tabbed section to set your preferences for mouse movement.

Table 10–15 lists the mouse motion preferences that you can modify:

TABLE 10–15 Mouse Motion Preferences

Dialog Element	Description
Acceleration	Use the slider to specify the speed at which your mouse pointer moves on your screen when you move your mouse.
Sensitivity	Use the slider to specify how sensitive your mouse pointer is to movements of your mouse.
Threshold	Use the slider to specify the distance that you must move an item before the move action is interpreted as a drag-and-drop action.

Configuring Multimedia Keys

Use the Multimedia Keys preference tool to assign shortcut keys to an action.

Table 10–16 lists the shortcut key preferences that you can set for multimedia functions.

TABLE 10–16 Multimedia Keys Preferences

Dialog Element	Description
Multimedia keys table	To add the shortcut keys for an action, click on the action to select the action, then press the keys that you want to associate with the action. To disable the shortcut keys for an action, click on the action to select the action, then press Back Space.
Use PCM volume instead of Master volume	Select this option if you want to use Pulse Code Modulation (PCM) volume instead of Master volume.

Customizing Your Panels

The Panel Preferences preference tool enables you to configure the behavior of panels. Any changes that you make with the Panel Preferences preference tool affect all of your panels.

Table 10–17 lists the panel preferences that you can modify:

TABLE 10–17 Panel Preferences

Dialog Element	Description
Close drawer when launcher is clicked	Select this option if you want a drawer on a panel to close when you choose a launcher in the drawer.
Drawer and panel animation	Select this option if you want your panels and drawers to show and to hide in an animated style.
Animation speed	Select the speed of the panel animation from the drop-down list.

Changing Your Password

The Password preference tool enables you to change your login password. To change your login password, perform the following steps:

1. Start the Password preference tool. A **Query** dialog is displayed.
2. Enter the old password.
3. Enter the new password, then enter the new password again to confirm.

Your new password takes effect the next time you log in.

Choosing Your Preferred Applications

Use the Preferred Applications preference tool to specify the applications that you want the GNOME Desktop to use when the GNOME Desktop starts an application for you. For example, you can specify Xterm as your preferred terminal application. When you open the Desktop menu then choose New Terminal, Xterm starts.

You can customize the preferences for the Preferred Applications preference tool in the following functional areas.

- **Web Browser**
- **Text Editor**
- **Terminal**

Web Browser Preferences

Use the Web Browser tabbed section to configure your preferred web browser. The preferred web browser opens when you click on a URL. For example, the preferred web browser opens when you select a URL in an application, or when you select a URL launcher on the desktop.

Table 10–18 lists the preferred web browser preferences that you can modify.

TABLE 10–18 Preferred Web Browser Preferences

Dialog Element	Description
Select a Web Browser	Select this option if you want to use a standard web browser. Use the drop-down combination box to select your preferred web browser.
Custom Web Browser	Select this option if you want to use a custom web browser.
Command	Enter the command to execute to start the custom web browser. To enable the browser to display a URL that you click on, include "%s" after the command.
Start in Terminal	Select this option to run the command in a terminal window. Select this option for a browser that does not create a window in which to run.

Text Editor Preferences

Use the Text Editor tabbed section to configure your preferred text editor.

Table 10–19 lists the preferred text editor preferences that you can modify.

TABLE 10–19 Preferred Text Editor Preferences

Dialog Element	Description
Select an Editor	Select this option if you want to use a standard text editor. Use the drop-down combination box to specify your preferred text editor.

TABLE 10–19 Preferred Text Editor Preferences (Continued)

Dialog Element	Description
Custom Editor	<p>Select this option if you want to use a custom text editor. A Custom Editor Properties dialog is displayed.</p> <ul style="list-style-type: none"> ■ Name: Type the name of the custom text editor. ■ Command: Enter the command to start the custom text editor. ■ This application can open multiple files: Select this option if the default text editor can open multiple files. ■ This application needs to be run in a shell: Select this option to run the command in a terminal window. Select this option for an editor that does not create a window in which to run. <p>After you specify a custom text editor, you can click on the Properties button to display the Custom Editor Properties dialog. You can use the dialog to modify the properties of the custom text editor.</p>
Use this editor to open text files in the file manager	Select this option if you want the file manager to start the custom text editor to display text files.

Terminal Preferences

Use the Terminal tabbed section to configure your preferred terminal.

Table 10–20 lists the preferred terminal preferences that you can modify.

TABLE 10–20 Preferred Terminal Preferences

Dialog Element	Description
Select a Terminal	Select this option if you want to use a standard terminal. Use the drop-down combination box to specify your preferred terminal.
Custom Terminal	Select this option if you want to use a custom terminal.
Command	Enter the command to execute to start the custom terminal.
Exec Flag	Enter the <code>exec</code> option to use with the command.

Setting Screen Resolution Preferences

Use the Screen Resolution preference tool to specify the resolution settings for your screen. Table 10–21 lists the screen resolution preferences that you can modify.

TABLE 10-21 Screen Resolution Preferences

Dialog Element	Description
Resolution	Select the resolution to use for the screen from the drop-down list.
Refresh rate	Select the screen refresh rate to use for the screen from the drop-down list.
Make default for this computer only	Select this option to make the screen resolution settings the default settings for the system that you are logged in to only.

Setting Screensaver Preferences

A screensaver is an application that you can use to replace the image on your screen when the screen is not in use. You can use screensavers in the following ways:

- Activate after a specified period of idle time.
- Activate when you lock your screen.
- Manage power used by your monitor when your system is idle.

You can customize the settings for the Mouse preference tool in the following functional areas:

- **Display Modes**
- **Advanced**

Display Modes Preferences

Use the **Display Modes** tabbed section to set display mode preferences.

Table 10-22 lists the display mode preferences that you can modify.

TABLE 10–22 Screensaver Display Mode Preferences

Dialog Element	Description
Mode	Use the drop-down list to specify the behavior of the screensaver application. Select from the following options: <ul style="list-style-type: none"> ■ Disable Screen Saver: Select this option if you do not want to use the screensaver application. ■ Blank Screen Only: Select this option if you want your screen to become blank when your screen locks. ■ Only One Screen Saver: Select this option if you want to display a single screensaver display from the display list when your screen locks. ■ Random Screen Saver: Select this option if you want to display a random selection of screensaver displays from the screensaver display list when your screen locks.
Display list	Select the screensaver display that you require from the list.
Blank After	Specify how long to wait after the last use of the mouse or keyboard, to activate the screensaver.
Cycle After	Specify how long to show a particular screensaver display before the next display.
Lock Screen After	Select this option if you want the screen to lock after the screensaver is activated. Use the spin box to specify the delay between the activation of the screensaver and when the screen locks.
Preview	Click on this button to preview the screensaver display that is selected in the screensaver display list. To stop the preview, press any key or click a mouse button.
Settings	Click on this button to display the options for the screensaver display that is selected in the screensaver display list.

Advanced Preferences

Use the **Advanced** tabbed section to set advanced screensaver preferences.

Table 10–23 lists the advanced screensaver preferences that you can modify.

TABLE 10–23 Advanced Screensaver Preferences

Dialog Element	Description
Grab Desktop Images	Some screensavers can take a screenshot of your screen, then manipulate the screenshot to create your screensaver display. Select this option to enable screensavers to take a screenshot of your screen.
Grab Video Frames	Some screensavers can capture a frame of video, then manipulate the captured image to create your screensaver display. If your system has a video capture card, select this option to enable screensavers to capture a frame of video.
Choose Random Image	Select this option to enable screensavers to use images from a directory that you select. Type the path for the directory in the field. Alternatively, click Browse to display a dialog from which you can select a directory.
Verbose Diagnostics	Select this option if you want to display screensaver diagnostic information.
Display Subprocess Errors	Select this option if you want to display errors related to screensaver subprocesses on screen.
Display Splash Screen at Startup	Select this option to if you want Xscreensaver to display a splash dialog when Xscreensaver starts.
Power Management Enabled	Select this option to enable power management of your monitor. Power management can reduce energy consumption by your monitor when you are not using the monitor.
Standby After	Specify how long to wait to put the monitor in standby mode. When the monitor is in standby mode, the screen is black.
Suspend After	Specify how long to wait to put the monitor in power-saving mode.
Off After	Specify how long to wait to switch off monitor.
Install Colormap	Select this option to install a private colormap when the screensaver is active. Use of a private colormap might improve the quality of the color in particular screensaver displays.
Fade to Black When Blanking	Select this option if you want your display to fade to black when the screensaver activates.
Fade from Black When Unblinking	Select this option if you want your display to fade from black to the screen contents when the screensaver stops.

TABLE 10–23 Advanced Screensaver Preferences (Continued)

Dialog Element	Description
Fade Duration	Specify how long to take to fade to black when the screensaver activates.

Configuring Sessions

The Sessions preference tool enables you to manage your sessions. You can set session preferences, and specify which applications to start when you start a session. You can configure sessions to save the state of applications in the GNOME Desktop, and to restore the state when you start another session. You can also use this preference tool to manage multiple GNOME sessions.

You can customize the settings for sessions and startup applications in the following functional areas:

- **Session Options**
- **Current Session**
- **Startup Programs**

Setting Session Preferences

Use the **Session Options** tabbed section to manage multiple sessions, and to set preferences for the current session.

Table 10–24 lists the session options that you can modify.

TABLE 10–24 Session Options

Dialog Element	Description
Show splash screen on login	Select this option to display a splash screen when you start a session.
Prompt on logout	Select this option to display a confirmation dialog when you end a session.

TABLE 10–24 Session Options (Continued)

Dialog Element	Description
Automatically save changes to session	<p>Select this option if you want the session manager to save the current state of your session. The session manager saves the session-managed applications that are open, and the settings associated with the session-managed applications. The next time that you start a session, the applications start automatically, with the saved settings.</p> <p>If you do not select this option, when you end you session the Logout Confirmation dialog displays a Save current setup option.</p>
Sessions	<p>Use this area of the dialog to manage multiple sessions in the GNOME Desktop, as follows:</p> <ul style="list-style-type: none">■ To create a new session, click on the Add button. The Add a new session dialog is displayed. Use this dialog to specify a name for your session.■ To change the name of a session, select the session in the Choose Current Session table. Click on the Edit button. The Edit session name dialog is displayed. Type a new name for your session.■ To delete a session, select the session in the Choose Current Session table. Click on the Delete button.

Setting Session Properties

Use the **Current Session** tabbed section to specify startup order values, and to choose restart styles for the session-managed applications in your current session.

Table 10–25 lists the session properties that you can configure.

TABLE 10–25 Session Properties

Dialog Element	Description
Order	<p>The Order property specifies the order in which the session manager starts session-managed startup applications. The session manager starts applications with lower order values first. The default value is 50.</p> <p>To specify the startup order of an application, select the application in the table. Use the Order spin box to specify the startup order value.</p>

TABLE 10–25 Session Properties (Continued)

Dialog Element	Description
Style	<p>The Style property determines the restart style of an application. To select a restart style for an application, select the application in the table, then choose one of the following styles:</p> <ul style="list-style-type: none">■ Normal Starts automatically when you start a GNOME session. Use the <code>kill</code> command to terminate applications with this restart style during a session.■ Restart Restarts automatically whenever you close or terminate the application. Choose this style for an application if the application must run continuously during your session. To terminate an application with this restart style, select the application in the table, then click on the Remove button.■ Trash Does not start when you start a GNOME session.■ Settings Starts automatically when you start a session. Applications with this style usually have a low startup order, and store your configuration settings for GNOME and session-managed applications.
Remove	Click on the Remove button to delete the selected application from the list. The application is removed from the session manager, and closed. Application that you delete are not started the next time that you start a session.
Apply	Click on the Apply button to apply changes to the startup order and the restart style.

Configuring Startup Applications

Use the **Startup Programs** tabbed section of the Sessions preference tool to specify non-session-managed *startup applications*. Startup applications are applications that start automatically when you start a session. You specify the commands that run the non-session-managed applications in the **Startup Programs** tabbed section. The commands execute automatically when you log in.

You can also start session-managed applications automatically. For more information, see “Setting Session Preferences” on page 181.

Table 10–26 lists the startup applications preferences that you can modify.

TABLE 10–26 Startup Programs Preferences

Dialog Element	Description
Additional startup programs	<p>Use this table to manage non-session-managed startup applications as follows:</p> <ul style="list-style-type: none">■ To add a startup application, click on the Add button. The Add Startup Program dialog is displayed. Enter the command to start the application in the Startup Command field. If you specify more than one startup application, use the Priority spin box to specify the startup order of the each application. The startup order is the order in which you want the startup applications to start.■ To edit a startup application, select the startup application, then click on the Edit button. The Edit Startup Program dialog is displayed. Use the dialog to modify the command and the startup order for the startup application.■ To delete a startup application, select the startup application, then click on the Delete button.

Customizing Keyboard Shortcuts

A *keyboard shortcut* is a key or combination of keys that provides an alternative to standard ways of performing an action.

Use the Shortcuts preference tool to display the default keyboard shortcuts. You can customize the default keyboard shortcuts to your requirements.

Table 10–27 lists the keyboard shortcut settings that you can customize.

TABLE 10–27 Keyboard Shortcuts Preferences

Dialog Element	Description
Text editing shortcuts	<p>Select one of the following settings:</p> <ul style="list-style-type: none">■ Default: Use this setting for standard shortcut keys.■ Emacs: Use this setting for Emacs shortcut keys.

TABLE 10–27 Keyboard Shortcuts Preferences *(Continued)*

Dialog Element	Description
Desktop shortcuts	<p>This table lists actions and the shortcut keys that are associated with each action.</p> <p>To change the shortcut keys for an action, click on the action to select the action, then click on the shortcut for the action. Press the keys that you want to associate with the action.</p> <p>To disable the shortcut keys for an action, click on the action to select the action, then click on the shortcut for the action. Press Back Space.</p>

Configuring Printers

The Printers preference tool enables you to configure printers for the GNOME Desktop. You can also add a new printer if you have `root` access. Follow the online instructions from the **Add a Printer** assistant.

Setting Session Sharing Preferences

The Remote Desktop preference tool enables you to share a GNOME Desktop session between multiple users, and to set session-sharing preferences.

Table 10–28 lists the session-sharing preferences that you can set. These preferences have a direct impact of the security of your system.

TABLE 10–28 Session Sharing Preferences

Dialog Element	Description
Allow other users to view your desktop	Select this option to enable remote users to view your session. All keyboard, pointer, and clipboard events from the remote user are ignored.
Allow other users to control your desktop	Select this option to enable other to access and control your session from a remote location.

TABLE 10–28 Session Sharing Preferences (Continued)

Dialog Element	Description
Users can view your desktop at this web address: <i>web address</i>	Click on the web address link to send your system web address by email to a remote user.
When a user tries to view or control your desktop	Select the following security considerations when a user tries to view or control your session: <ul style="list-style-type: none">■ Ask you for confirmation: Select this option if you want remote users to ask you for confirmation when they want to share your session. This option enables you to be aware of other users who connect to your session. You can also decide what time is suitable for the remote user to connect to your session.■ Ensure the user is using encryption: Select this option if you require that all clients who connect to your session use encryption. This option is provided so that you may make the policy decision on whether unencrypted connections are allowed.■ Require the user to enter this password: Select this option to authenticate the remote user if authentication is used. This option provides an extra level of security.
Password	Enter the password that the client who attempts to view or control your session must enter.

Setting Sound Preferences

The Sound preference tool enables you to control when the GNOME sound server starts. You can also specify which sounds to play when particular events occur.

You can customize the settings for the Sound preference tool in the following functional areas:

- **General**
- **Sound Events**

General Sound Preferences

Use the **General** tabbed section of the Sound preference tool to specify when to launch the GNOME sound server. You can also enable sound event functions.

Table 10–29 lists the general sound preferences that you can modify.

TABLE 10–29 General Sound Preferences

Dialog Element	Description
Enable sound server startup	Select this option to start the GNOME sound server when you start a GNOME session. When the sound server is active, the GNOME Desktop can play sounds.
Sounds for events	Select this option to play sounds when particular events occur in the GNOME Desktop. You can select this option only if the Enable sound server startup option is selected.

Sound Event Preferences

Use the **Sound Events** tabbed section of the Sound preference tool to associate particular sounds with particular events.

Note – You must select the **Enable sound server startup** option, and the **Sounds for events** option before you can access the **Sound Events** tabbed section.

Table 10–30 lists the sound events preferences that you can modify.

TABLE 10–30 Sound Event Preferences

Dialog Element	Description
Sounds table	Use the Sounds table to associate particular sounds with particular events. The Event column displays a hierarchical list of events that can occur. To expand a category of events, click on the right arrow beside a category of events. The File to play column lists the sound file that plays when the event occurs.
Play	Click on this button to play the sound file that is associated with the selected event.
Sound file drop-down combination box, Browse	To associate a sound with an event, select the event in the Sounds table. Enter the name of the sound file that you want to associate with the selected event in the drop-down combination box. Alternatively, click Browse to display a Select sound file dialog. Use the dialog to specify the sound file that you want to associate with the selected event. Note – You can only associate sound files in .wav format with events.

Customizing Themes

A theme is a group of coordinated settings that specifies the visual appearance of a part of the GNOME Desktop. You can choose themes to change the appearance of the GNOME Desktop. Use the Theme preference tool to select a theme. You can choose from a list of available themes. The list of available themes includes several themes for users with accessibility requirements.

A theme contains settings that affect different parts of the GNOME Desktop, as follows:

Controls	The controls setting for a theme determines the visual appearance of windows, panels, and applets. The controls setting also determines the visual appearance of the GNOME-compliant interface items that appear on windows, panels, and applets, such as menus, icons, and buttons. Some of the controls setting options that are available are designed for special accessibility needs. You can choose an option for the controls setting from the Controls tabbed section in the Theme preference tool.
Window frame	The window frame setting for a theme determines the appearance of the frames around windows only. You can choose an option for the window frame setting from the Window Border tabbed section in the Theme preference tool.
Icon	The icon setting for a theme determines the appearance of the icons on panels and the desktop background. You can choose an option for the icon setting from the Icons tabbed section in the Theme preference tool.

To Create a Custom Theme

The themes that are listed in the Theme preferences tool are different combinations of controls options, window frame options, and icon options. You can create a custom theme that uses different combinations of controls options, window frame options, and icon options.

To create a custom theme, perform the following steps:

1. Start the Theme preference tool.
2. Select a theme in the list of themes.
3. Click on the Details button. A **Theme Details** dialog is displayed.

4. Select the controls option that you want to use in the custom theme from the list in the **Controls** tabbed section. The list of available controls options includes several options for users with accessibility requirements.
5. Click on the **Window Border** tab to display the **Window Border** tabbed section. Select the window frame option that you want to use in the custom theme from the list of available options. The list of available window frame options includes several options for users with accessibility requirements.
6. Click on the **Icons** tab to display the **Icons** tabbed section. Select the icons option that you want to use in the custom theme from the list of available options. The list of available icons options includes several options for users with accessibility requirements.
7. Click Close to close the **Theme Details** dialog.
8. On the Theme preferences tool, click on the Save theme button. A **Save theme to disk** dialog is displayed.
9. Type a name and a short description for the custom theme in the dialog, then click Save. The custom theme now appears in your list of available themes.

To Install a New Theme

You can add a theme to the list of available themes. The new theme must be an archive file that is tarred and zipped. That is, the new theme must be a `.tar.gz` file.

To install a new theme, perform the following steps:

1. Start the Theme preference tool.
2. Click on the Install theme button. An **Install New Theme** dialog is displayed.
3. Enter the location of the theme archive file in the drop-down combination box. Alternatively, to browse for the file, click on the Browse button. When you have selected the file, click OK.
4. Click on the Install button to install the new theme.

To Install a New Theme Option

You can install new controls options, window frame options, or icons options. You can find many controls options on the Internet.

To install a new controls option, window frame option, or icons option, perform the following steps:

1. Start the Theme preference tool.
2. Click on the Details button. An **Theme Details** dialog is displayed.

3. Click on the tab for the type of theme that you want to install. For example, to install an icons option, click on the **Icons** tab.
4. Click on the Install new theme button. An **Install New Theme** dialog is displayed.
5. Enter the location of the option archive file in the drop-down combination box. Alternatively, to browse for the file, click on the Browse button. When you have selected the file, click OK.
6. Click on the Install button to install the new option.

To Delete a Theme Option

You can delete controls options, window frame options, or icons options.

To delete a controls option, window frame option, or icons option, perform the following steps:

1. Start the Theme preference tool.
2. Click on the Details button. A **Theme Details** dialog is displayed.
3. Click on the tab for the type of option that you want to delete.
4. Click on the Go to theme folder button. A file manager window opens on the default option folder.
5. Use the file manager window to delete the option.

Customizing Windows

Use the Windows preference tool to customize window behavior for the GNOME Desktop.

Table 10–31 lists the windows preferences that you can modify.

TABLE 10–31 Windows Preferences

Dialog Element	Description
Select windows when the mouse moves over them	Select this option to give focus to a window when you point to the window. The window retains focus until you point to another window.
Raise selected windows after an interval	Select this option to raise windows a short time after the window receives focus.

TABLE 10-31 Windows Preferences (Continued)

Dialog Element	Description
Interval before raising	Specify the interval to wait before raising a window that has received focus.
Double-click titlebar to perform this action	Select the behavior that you want to occur when you double-click on a window titlebar. Select one of the following options: <ul style="list-style-type: none"><li data-bbox="740 527 1065 548">■ Roll up: Shades the window.<li data-bbox="740 558 1130 579">■ Maximize: Maximizes the window.
To move a window, press-and-hold this key then grab the window	Select the key to press-and-hold when you drag a window to move the window.

GNOME Desktop Applications

This section describes how to start GNOME Desktop applications in the following chapters.

- *Starting Applications*

Read this chapter to find out how to start the applications in the GNOME Desktop.

Starting Applications

This chapter describes how to start your applications, and where to find the applications in the GNOME Desktop menu structure.

- “Starting an Application” on page 195
- “Where to Find Applications” on page 195

Starting an Application

To start an application, choose Applications from the Main Menu. Choose the application that you require from the submenu.

You can also access the Applications menu from the Menu Bar.

Where to Find Applications

Table 11-1 lists the applications in the GNOME Desktop, and where you can find each application in the menu structure.

TABLE 11-1 Location of Applications in GNOME Desktop Menu Structure

Applications	Menu Path
Archive Manager	Applications → Accessories → Archive Manager
Backup	Applications → System Tools → Backup

TABLE 11-1 Location of Applications in GNOME Desktop Menu Structure *(Continued)*

Applications	Menu Path
Boot Floppy Generator	Applications → System Tools → Administration → Boot Floppy Generator
Calculator	Applications → Accessories → Calculator
CD Player	Applications → Multimedia → CD Player
Character Map	Applications → Accessories → Character Map
Configuration Editor	Applications → System Tools → Configuration Editor
Dictionary	Applications → Accessories → Dictionary
Diagram Editor	Applications → Graphics → Diagram Editor
Digital Camera Browser	Applications → Multimedia → Digital Camera Browser
Disk Analyzer	Applications → System Tools → Disk Analyzer
Disk Partitioner	Applications → System Tools → Administration → Disk Partitioner
Driver Installer	Applications → System Tools → Administration → Driver Installer
Email and Calendar	Applications → Internet → Email and Calendar Alternatively, choose Email and Calendar from the Main Menu.
File Backups	Applications → System Tools → Administration → File Backups
File Restores	Applications → System Tools → Administration → File Restores
Floppy Formatter	Applications → System Tools → Floppy Formatter
Image Editor	Applications → Graphics → Image Editor
Image Organizer	Applications → Graphics → Image Organizer
Image Viewer	Applications → Graphics → Image Viewer
Instant Messenger	Applications → Internet → Instant Messenger
Java Media Player	Applications → Multimedia → Java Media Player
Java Web Start	Applications → Internet → Java Web Start
Login Screen Setup	Applications → System Tools → Administration → Login Screen Setup
Movie Player	Applications → Multimedia → Movie Player

TABLE 11-1 Location of Applications in GNOME Desktop Menu Structure *(Continued)*

Applications	Menu Path
Network Places	Applications → Internet → Network Places
New Login	Applications → System Tools → New Login
New Login in a Nested Window	Applications → System Tools → New Login in a Nested Window
Online Update	Applications → System Tools → Online Update
PDF Document Viewer	Applications → Graphics → PDF Document Viewer
PostScript Viewer	Applications → Graphics → PostScript Viewer
Project Manager	Applications → Office → Project Manager
Real Player	Applications → Multimedia → Real Player
Software Installer	Applications → System Tools → Administration → Software Installer
Sound Recorder	Applications → Multimedia → Sound Recorder
Source Editor	Applications → Accessories → Source Editor
StarOffice 7	Choose StarOffice 7 from the Main Menu.
StarOffice 7 Presentation	Applications → Office → StarOffice 7 Presentation
StarOffice 7 Spreadsheet	Applications → Office → StarOffice 7 Spreadsheet
StarOffice 7 Text Document	Applications → Office → StarOffice 7 Text Document
Sun Java System Instant Messaging	Applications → Internet → Sun Java System Instant Messaging
System Monitor	Applications → System Tools → System Monitor
Terminal	Applications → System Tools → Terminal
Text Editor	Applications → Accessories → Text Editor
Video Conferencing	Applications → Internet → Video Conferencing
Volume Control	Applications → Multimedia → Volume Control
Volume Manager	Applications → System Tools → Administration → Volume Manager
Web Browser	Applications → Internet → Web Browser Alternatively, choose Web Browser from the Main Menu.

Glossary

applet	An applet is a small, interactive application that resides within a panel, for example the CD Player. Each applet has a simple user interface that you can operate with the mouse or keyboard.
desktop	The part of the GNOME Desktop where there are no interface graphical items, such as panels and windows.
desktop background	The image or color that is applied to your desktop.
desktop object	An icon on your desktop that you can use to open your files, folders, and applications. You can use desktop objects to provide convenient access to files, folders, and applications that you use frequently.
DNS name	A unique alphabetic identifier for a computer on a network.
drawer	A drawer is a sliding extension to a panel that you can open or close from a drawer icon.
format	To format media is to prepare the media for use with a particular file system. When you format media, you overwrite any existing information on the media.
GNOME-compliant application	An application that uses the standard GNOME programming libraries is called a GNOME-compliant application. For example, Nautilus file manager and gedit text editor are GNOME-compliant applications.
IP address	A unique numeric identifier for a computer on a network.
keyboard shortcut	<i>A keyboard shortcut</i> is a key or combination of keys that provides an alternative to standard ways of performing an action.
launcher	A launcher starts a particular application, executes a command, or opens a file. A launcher can reside in a panel or in a menu.
menubar	A menubar is a bar at the top of an application window that contains the menus for the application.

MIME type	A Multipurpose Internet Mail Extension (MIME) type identifies the format of a file. The MIME type enables applications to read the file. For example, an email application can use the <code>image/png</code> MIME type to detect that a Portable Networks Graphic (PNG) file is attached to an email.
mount	To mount is to make a file system available for access. When you mount a file system, the file system is attached as a subdirectory to your file system.
pane	A pane is a subdivision of a window. For example, the Nautilus window contains a side pane and a view pane.
preference tool	A dedicated software tool that controls a particular part of the behavior of the GNOME Desktop.
shortcut keys	Shortcut keys are keystrokes that provide a quick way to perform an action.
stacking order	The stacking order is the order in which windows are stacked on top of each other on your screen.
statusbar	A statusbar is a bar at the bottom of a window that provides information about the current state of what you are viewing in the window.
symbolic link	A special type of file that points to another file or folder. When you perform an action on a symbolic link, the action is performed on the file or folder to which the symbolic link points.
toolbar	A toolbar is a bar that contains buttons for the most commonly-used commands in an application. Typically, a toolbar appears under a menubar.
Uniform Resource Identifier	A Uniform Resource Identifier (URI) is a string that identifies a particular location in a file system or on the Web. For example, the address of a web page is a URI.
Uniform Resource Locator	A Uniform Resource Locator (URL) is the address of a particular location on the Web.
view	A Nautilus component that enables you to display a folder in a particular way. For example, Nautilus contains an icon view which enables you to display the contents of a folder as icons. Nautilus also contains a list view which enables you to display the contents of a folder as a list.
viewer component	A Nautilus component that enables you to display a particular type of file in the view pane. A viewer component might add menu items that are relevant to the file type to the file manager menus. A viewer component might also enable you to use the Nautilus zoom buttons to change the size of the item in the view pane.

workspace

A workspace is a discrete area in the GNOME Desktop in which you can work.

Index

A

- access keys, 26
- accessibility
 - bounce keys, 169
 - configuring keyboard, 167
 - mouse keys, 170
 - repeat keys, 168
 - slow keys, 169
 - sticky keys, 168
 - toggle keys, 169
- AccessX, *See* preference tools, Keyboard
 - Accessibility
- action buttons, *See* buttons
- applets
 - adding to panel, 58
 - getting help, 43
 - introduction, 58
 - modifying preferences, 59
 - Notification Area, 67
 - overview, 32
 - selecting, 59
 - Window List, 87
 - Workspace Switcher, 88
- applications
 - help, 43
 - overview, 41
 - terminating, 64

B

- backgrounds
 - adding colors, 130

backgrounds (Continued)

- adding patterns, 129
 - changing desktop background, 149
 - changing screen component, 129
 - customizing desktop background, 158
- ## basic skills
- keyboard skills, 23
 - mouse skills, 19
 - using windows, 27
- ## burning CDs, *See* writing CDs
- ## buttons
- adding to panel, 63
 - Force Quit, 64
 - Lock, 64
 - Log Out, 65
 - Run, 65
 - Screenshot, 66
 - Search, 66
 - Show Desktop, 66

C

- CDs, writing, 133
- closing windows, 91

D

- default applications, *See* preferred applications
- desktop
 - adding a file or folder to, 144
 - adding emblems to objects, 146

desktop (Continued)

- adding launchers, 143
 - adding notes to objects, 146
 - adding symbolic links, 143
 - background, changing pattern or color, 149
 - changing icon of a desktop object, 146
 - changing permissions of object, 146
 - copying a file or folder to, 144
 - creating a folder on, 145
 - customizing background, 158
 - deleting an object from, 145
 - desktop objects, 142
 - introduction, 141
 - moving a file or folder to, 144
 - opening objects, 143
 - overview, 40
 - removing an object from, 145
 - renaming object, 145
 - resizing icons, 147
 - selecting objects, 142
 - using Desktop menu, 148
 - using Trash, 147
 - viewing properties of object, 145
- ## Desktop menu
- description, 148
 - illustration, 148
- ## desktop objects
- adding emblems, 146
 - adding notes to, 146
 - changing icons, 146
 - changing permissions, 146
 - deleting, 145
 - files and folders, 144
 - launchers, 143
 - opening, 143
 - removing, 145
 - renaming, 145
 - resizing icons, 147
 - selecting, 142
 - symbolic links, 143
 - viewing properties, 145
- ## drawers
- adding objects to, 69
 - adding to panel, 69
 - closing, 68
 - modifying properties, 69
 - opening, 68

E

- ### emblems
- adding new, 117
 - adding to desktop objects, 146
 - adding to file, 117
 - adding to folder, 117
 - introduction, 99
- ### events, associating sounds with, 186

F

- ### file manager
- assigning actions to files, 123
 - audio view
 - illustration, 120
 - bookmarks, 108
 - changing backgrounds, 129
 - changing permissions, 114
 - copying files and folders, 111
 - creating folders, 112
 - creating symbolic link, 113
 - customizing, 125
 - deleting files or folders, 113
 - displaying folders, 101
 - drag-and-drop, 109
 - duplicating files and folders, 112
 - emblems
 - See* emblems
 - executing default actions for files, 103
 - executing non-default actions for files, 104
 - executing other actions for files, 104
 - FTP sites
 - See* FTP sites
 - History, 108
 - icon view
 - arranging files in, 120
 - illustration, 96
 - icons
 - caption preferences, 127
 - changing, 117
 - introduction, 99
 - resizing, 122
 - introduction, 95
 - list view
 - illustration, 119
 - managing files and folders, 109
 - modifying actions, 123

- file manager (Continued)
 - modifying appearance of files and folders, 117
 - moving files and folders, 111
 - navigating, 101
 - navigating history list, 107
 - network places
 - See* network places
 - notes
 - adding, 115
 - deleting, 115
 - opening files, 103
 - overview, 38
 - preferences
 - behavior, 126
 - icon captions, 127
 - introduction, 125
 - preference tool, 164
 - preview, 128
 - views, 125
 - renaming folders, 112
 - running scripts, 134
 - selecting files and folders, 110
 - side pane
 - introduction, 99
 - special URI locations, 106
 - Trash
 - See* Trash
 - Tree, using, 102
 - view pane
 - See* view pane
 - viewing files in view pane, 103
 - viewing properties, 114
 - views
 - choosing, 120
 - introduction, 119
 - modifying behavior, 122
 - window components, showing and hiding, 130
 - windows, 96
 - writing CDs, 133
 - zooming in and out, 118
- file types
 - adding, 162
 - configuring, 161
 - editing, 162
- focus, giving to a window, 90

- fonts
 - applications, 164
 - desktop, 164
 - previewing, 165
 - rendering, 164
 - terminal, 164
 - window title, 164
- Force Quit button, 64
- FTP sites, accessing, 104

G

- GNOME Desktop components, introducing, 29
- GNOME Desktop preference tools, *See* preference tools
- GTK+ themes, *See* themes, controls options

H

- help
 - applets, 43
 - applications, 43
 - GNOME Desktop topics, 43
 - how to find, 42
 - starting help system, 43

I

- icon themes, *See* themes, icons options
- Internet
 - configuring connection, 166, 185

K

- keyboard
 - basic skills, 23
 - configuring accessibility options, 167
 - configuring general preferences, 170
 - configuring sound preferences, 171
- keyboard shortcuts, configuring, 184

L

- language, logging in in different, 46
- Launch menu, *See* Main Menu
- launchers
 - adding to panel, 60, 73
 - modifying properties, 63
- Lock button, 46, 64
- locking panel objects, 58
- locking screen, 46, 64
- Log Out button, 65
- logging in
 - to session, 46
 - to session in different language, 46
- logging out, 49

M

- Main Menu
 - adding to panel, 77
 - introduction, 76
 - opening, 77
- maximizing windows, 91
- Menu Bar
 - adding to panel, 77
 - introduction, 77
- menu item popup menu
 - description, 72
 - illustration, 73
- menus
 - Actions menu, 74
 - adding, 78
 - adding launchers to, 79
 - adding to panel, 67, 73
 - Applications menu, 73
 - copying launchers to, 79
 - customizing, 78
 - deleting menu items, 80
 - Desktop menu, 148
 - editing menu items, 80
 - editing properties, 80
 - features, 72
 - in applications, customizing
 - appearance, 172
 - introduction, 71
 - Main Menu
 - See* Main Menu

menus (Continued)

- Menu Bar
 - See* Menu Bar
 - menu item popup menu, 72
 - overview, 34
 - Window Menu, 86
- Metacity themes, *See* themes, window frame options
- minimizing, windows, 90
- mouse
 - action terminology, 21
 - actions, 20
 - basic skills, 19
 - button conventions, 19
 - configuring, 172
 - pointers, 21
- moving windows, 92

N

- Nautilus desktop, *See* desktop
- Nautilus file manager, *See* file manager
- network places, accessing, 105
- network proxy
 - setting preferences, 166, 185
- NFS servers, *See* Unix network notes
 - adding to desktop objects, 146
 - adding to files and folders, 115
 - deleting, 115
- Notification Area applet, 67

P

- panel object popup menu, illustration, 56
- panel objects
 - adding, 56
- applets
 - See* applets
- drawers
 - See* drawers
- Force Quit button, 64
- interacting with, 55
- launchers
 - See* launchers
- Lock button, 64

- panel objects (Continued)
 - locking, 58
 - Log Out button, 65
 - menus, 67
 - modifying properties, 56
 - moving, 57
 - Notification Area applet, 67
 - removing, 58
 - Run button, 65
 - Screenshot button, 66
 - Search button, 66
 - Show Desktop button, 66
 - panels
 - adding new, 52
 - changing background, 55
 - customizing behavior and appearance, 175
 - deleting, 55
 - hiding, 52
 - interacting with, 52
 - introduction, 51
 - managing, 52
 - modifying properties, 53
 - moving, 52
 - overview, 31
 - panel objects
 - See* panel objects
 - panes, resizing, 27
 - permissions
 - and emblems, 100
 - changing file and folder, 114
 - displaying as characters, 128
 - displaying in octal notation, 128
 - introduction, 114
 - pointers, *See* mouse pointers
 - preference tools
 - Background, 158
 - CD Database, 159
 - File Associations, 161
 - Folder Options, 164
 - Font, 164
 - Internet, 166, 185
 - Keyboard Accessibility, 167
 - Keyboard Behavior, 170
 - Keyboard Layout, 171
 - Menus & Toolbars, 172
 - Mouse, 172
 - Multimedia Keys, 174
 - overview, 41
 - preference tools (Continued)
 - Panel Preferences, 175
 - Preferred Applications, 175
 - Screen Resolution, 177
 - Screensaver, 178
 - Sessions, 47, 181
 - Shortcuts, 184
 - Sound, 186
 - Theme, 188
 - Windows, 190
 - preferences, file manager, *See* file manager
 - preferences
 - preferences
 - preferred applications
 - terminal, 177
 - text editor, 176
 - web browser, 176
 - proxy
 - setting preferences, 166, 185
- ## R
- removable media
 - displaying media contents, 131
 - displaying media properties, 131
 - ejecting, 133
 - formatting floppy diskette, 131, 135
 - introduction, 130
 - mounting, 130
 - resizing windows, 91
 - restoring, windows, 91
 - rolling up windows, 92
 - Run Application dialog, using, 74
 - Run button, 65
- ## S
- Samba servers, *See* Windows network
 - screensaver, setting preferences, 178
 - Screenshot button, 66
 - screenshots, taking, 75
 - scripts, running from file manager, 134
 - Search button, 66
 - services
 - adding, 163
 - configuring, 161
 - editing, 162

- sessions
 - browsing applications, 48
 - configuring screensaver, 178
 - different language, logging in, 46
 - ending, 49
 - locking screen, 46
 - logging in, 46
 - logging out, 49
 - login behavior, 47
 - logout behavior, 47
 - managing, 47
 - preferences, 181
 - saving settings, 48
 - setting options, 181
 - setting properties, 182
 - starting, 45
 - using startup applications, 48
- shading windows, *See* rolling up windows
- shortcut keys
 - application, 25
 - configuring, 184
 - general, 23
 - panel, 25
 - window, 24
- Show Desktop button, 66
- side pane, *See* file manager
- sound
 - associating events with sounds, 186
 - configuring keyboard preferences, 171
 - setting preferences, 186
- sound server, 186
- special URI locations
 - accessing, 106
 - and launchers, 60
- special URIs, launchers, 63
- startup applications
 - customizing, 181
 - non-session-managed, 48, 183
 - session-managed, 47, 182
- startup programs, *See* startup applications
- symbolic link
 - to desktop object, creating, 143
 - to file or folder, creating, 113
- symbolic links, and emblems, 101

T

- tables, using, 27
- terminal, preferred application, 177
- terminating applications, 64
- text editor, preferred application, 176
- themes
 - controls options
 - introduction, 188
 - icons options
 - introduction, 188
 - setting controls options, 188
 - setting icons options, 188
 - setting window frame options, 188
 - window frame options
 - introduction, 188
- toolbars, customizing appearance, 172
- top edge panel, window list icon, 89
- Trash
 - displaying, 116, 147
 - emptying, 116, 148
 - introduction, 116
 - moving files or folders to, 112
 - using on desktop, 147
- Tree, using, 102

U

- URI, special, *See* special URI locations

V

- view pane
 - introduction, 98
 - viewing files in, 103
- viewer components, 98, 103, 119

W

- web browser, preferred application, 176
- Window List applet
 - grouping buttons, 88
 - introduction, 87
 - window status information, 87
- window lists
 - top edge panel, 89

- window lists (Continued)
 - Window List applet, 87
- window manager, customizing, 190
- windows
 - applets and menus for working with, 85
 - closing, 91
 - frame control elements, 84
 - frames, 84
 - giving focus to, 90
 - introduction, 81
 - manipulating, 90
 - maximizing, 91
 - minimizing, 90
 - moving, 92
 - moving to another workspace, 93
 - overview, 35
 - putting on all workspaces, 93
 - resizing, 91
 - resizing panes, 27
 - restoring, 91
 - rolling up, 92
 - setting frame theme options, 188
 - themes, 84
 - types of, 82
 - using tables, 27
 - Window List applet
 - See* Window List applet
 - window managers, 82
 - Window Menu, 86
- Workspace Switcher applet, 88
- workspaces
 - adding, 94
 - deleting, 94
 - introduction, 81
 - manipulating, 93
 - moving windows to, 93
 - naming, 94
 - overview, 37
 - specifying number of, 38
 - switching between, 37, 93
 - Workspace Switcher applet, 88
- writing CDs, 133

X

XScreenSaver, *See* screensaver

