



Transferring Messaging Server Configuration Data to a New Directory Server Host Without Reinstalling Messaging Server

Sun Java™ Enterprise System Technical Note



Sun Microsystems, Inc.
4150 Network Circle
Santa Clara, CA 95054
U.S.A.

Part No: 819-7603-10
August 2006

Copyright 2006 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. All rights reserved.

Sun Microsystems, Inc. has intellectual property rights relating to technology embodied in the product that is described in this document. In particular, and without limitation, these intellectual property rights may include one or more U.S. patents or pending patent applications in the U.S. and in other countries.

U.S. Government Rights – Commercial software. Government users are subject to the Sun Microsystems, Inc. standard license agreement and applicable provisions of the FAR and its supplements.

This distribution may include materials developed by third parties.

Parts of the product may be derived from Berkeley BSD systems, licensed from the University of California. UNIX is a registered trademark in the U.S. and other countries, exclusively licensed through X/Open Company, Ltd.

Sun, Sun Microsystems, the Sun logo, the Solaris logo, the Java Coffee Cup logo, docs.sun.com, Java, and Solaris are trademarks or registered trademarks of Sun Microsystems, Inc. in the U.S. and other countries. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. in the U.S. and other countries. Products bearing SPARC trademarks are based upon an architecture developed by Sun Microsystems, Inc.

The OPEN LOOK and Sun™ Graphical User Interface was developed by Sun Microsystems, Inc. for its users and licensees. Sun acknowledges the pioneering efforts of Xerox in researching and developing the concept of visual or graphical user interfaces for the computer industry. Sun holds a non-exclusive license from Xerox to the Xerox Graphical User Interface, which license also covers Sun's licensees who implement OPEN LOOK GUIs and otherwise comply with Sun's written license agreements.

Products covered by and information contained in this publication are controlled by U.S. Export Control laws and may be subject to the export or import laws in other countries. Nuclear, missile, chemical or biological weapons or nuclear maritime end uses or end users, whether direct or indirect, are strictly prohibited. Export or reexport to countries subject to U.S. embargo or to entities identified on U.S. export exclusion lists, including, but not limited to, the denied persons and specially designated nationals lists is strictly prohibited.

DOCUMENTATION IS PROVIDED "AS IS" AND ALL EXPRESS OR IMPLIED CONDITIONS, REPRESENTATIONS AND WARRANTIES, INCLUDING ANY IMPLIED WARRANTY OF MERCHANTABILITY, FITNESS FOR A PARTICULAR PURPOSE OR NON-INFRINGEMENT, ARE DISCLAIMED, EXCEPT TO THE EXTENT THAT SUCH DISCLAIMERS ARE HELD TO BE LEGALLY INVALID.

Copyright 2006 Sun Microsystems, Inc. 4150 Network Circle, Santa Clara, CA 95054 U.S.A. Tous droits réservés.

Sun Microsystems, Inc. détient les droits de propriété intellectuelle relatifs à la technologie incorporée dans le produit qui est décrit dans ce document. En particulier, et ce sans limitation, ces droits de propriété intellectuelle peuvent inclure un ou plusieurs brevets américains ou des applications de brevet en attente aux États-Unis et dans d'autres pays.

Cette distribution peut comprendre des composants développés par des tierces personnes.

Certains composants de ce produit peuvent être dérivées du logiciel Berkeley BSD, licenciés par l'Université de Californie. UNIX est une marque déposée aux États-Unis et dans d'autres pays; elle est licenciée exclusivement par X/Open Company, Ltd.

Sun, Sun Microsystems, le logo Sun, le logo Solaris, le logo Java Coffee Cup, docs.sun.com, Java et Solaris sont des marques de fabrique ou des marques déposées de Sun Microsystems, Inc. aux États-Unis et dans d'autres pays. Toutes les marques SPARC sont utilisées sous licence et sont des marques de fabrique ou des marques déposées de SPARC International, Inc. aux États-Unis et dans d'autres pays. Les produits portant les marques SPARC sont basés sur une architecture développée par Sun Microsystems, Inc.

L'interface d'utilisation graphique OPEN LOOK et Sun a été développée par Sun Microsystems, Inc. pour ses utilisateurs et licenciés. Sun reconnaît les efforts de pionniers de Xerox pour la recherche et le développement du concept des interfaces d'utilisation visuelle ou graphique pour l'industrie de l'informatique. Sun détient une licence non exclusive de Xerox sur l'interface d'utilisation graphique Xerox, cette licence couvrant également les licenciés de Sun qui mettent en place l'interface d'utilisation graphique OPEN LOOK et qui, en outre, se conforment aux licences écrites de Sun.

Les produits qui font l'objet de cette publication et les informations qu'il contient sont régis par la législation américaine en matière de contrôle des exportations et peuvent être soumis au droit d'autres pays dans le domaine des exportations et importations. Les utilisations finales, ou utilisateurs finaux, pour des armes nucléaires, des missiles, des armes chimiques ou biologiques ou pour le nucléaire maritime, directement ou indirectement, sont strictement interdites. Les exportations ou réexportations vers des pays sous embargo des États-Unis, ou vers des entités figurant sur les listes d'exclusion d'exportation américaines, y compris, mais de manière non exclusive, la liste de personnes qui font objet d'un ordre de ne pas participer, d'une façon directe ou indirecte, aux exportations des produits ou des services qui sont régis par la législation américaine en matière de contrôle des exportations et la liste de ressortissants spécifiquement désignés, sont rigoureusement interdites.

LA DOCUMENTATION EST FOURNIE "EN L'ETAT" ET TOUTES AUTRES CONDITIONS, DECLARATIONS ET GARANTIES EXPRESSES OU TACITES SONT FORMELLEMENT EXCLUES, DANS LA MESURE AUTORISEE PAR LA LOI APPLICABLE, Y COMPRIS NOTAMMENT TOUTE GARANTIE IMPLICITE RELATIVE A LA QUALITE MARCHANDE, A L'APTITUDE A UNE UTILISATION PARTICULIERE OU A L'ABSENCE DE CONTREFACON.

Transferring Messaging Server Configuration Data to a New Directory Server Host Without Reinstalling Messaging Server

This document describes how to migrate Messaging Server configuration data when you install a new Directory Server. It is assumed that Messaging Server stores its configuration data on the Directory Server being upgraded or moved to a new host.

This technical note contains the following sections:

- [“Technical Note Revision History”](#) on page 3
- [“Transferring Messaging Server Configuration Data to a New Directory Server”](#) on page 3
- [“Documentation, Support, and Training”](#) on page 8

Technical Note Revision History

Version	Date	Description of Changes
2	August 2006	Revision to apply this technical note to Messaging Server 6.
1	September 2003	Initial release of this technical note.

Transferring Messaging Server Configuration Data to a New Directory Server

This section explains why you might need to transfer Messaging Server data, lists the types of data to be migrated, and specifies the key conditions that determine which migration steps to follow.

Because each Messaging Server deployment is different—for example, all servers may be in a stand-alone configuration, or they may be in a replicated configuration—we will only describe

the general concepts, goals, and procedures in migrating Messaging Server configuration data between Directory Server hosts. You may have to modify these procedures for your own Messaging Server system.

Migration Assumptions

This document makes the following assumptions:

- You have an existing Messaging Server installation that uses Directory Server to store user and configuration data.
- You want to avoid upgrading or reinstalling Messaging Server.
- You are installing a new Directory Server into a different host, or, if installing on the same host, you are installing the Directory Server software into a different server root path than the one used by the Directory Server.

Reasons for Installing a New Directory Server

You might need to move your Directory Server and, thus, to migrate your Messaging Server configuration data, in the following situations:

- You want to upgrade Directory Server.
You might be upgrading Directory Server from one version to another—for example, from iPlanet Directory Server 5.x to Sun Java System Directory Server 6.x.
- You want to replace the original Directory Server host machine with a new machine.
You might reinstall Directory Server on a new host—without necessarily upgrading the software—when you need to modify the topology of your entire deployment. For example, you may be enlarging your deployment to encompass multiple hosts, and need to point Messaging Server to a new Directory Server host.
Or you may need to move Directory Server from one machine to another because you are upgrading hardware.

Types of Messaging Server Data to Migrate

When you install a new Directory Server, you must move the following Messaging Server data:

- User/group data
- Personal address book (PAB) data
- Messaging Server configuration data
- Messaging Server Domain Component (DC) tree. This applies only if you use a Schema 1 directory structure.

- Personal Information Store Database (PiServerDB)

Communications Express stores personal address-book data in LDAP entries under the distinguished name (DN) `o=PiServerDB`.

Migrating user/group, PAB, and DC tree data to a new Directory Server is a relatively simple task: you take user and PAB LDIF data from the original Directory Server and load it into the target Directory Server.

Migrating Messaging Server configuration data is much more problematic. This is the subject of this technical note.

The Key Condition for Using This Document!

Messaging Server configuration data is stored under the DN `o=netscape.root`. Directory Server skips over this DN when a Directory Server migration occurs.

For this reason, you cannot use standard Directory Server methods to migrate the configuration data. Instead, you must follow the steps in this document.

Messaging Server Versions

The Messaging Server version you are running may determine whether you need to use this document:

- All versions of Messaging Server prior to version 6.0 store their data in the `o=netscape.root` suffix.
- Messaging Server 6.0, 6.1, and 6.2 (Sun ONE Messaging Server and Sun Java System Messaging Server) can store configuration data under the DN `o=comms-config`. Configuration data stored under this DN can be migrated using standard methods.
- Messaging Server 6.3 stores configuration data in local files, not in the LDAP directory. If you are using Messaging Server 6.3, this document will no longer apply.

What Should You Do?

Find out where your Messaging Server configuration data is located in the directory.

Run the `configutil` program to obtain the value of the `local.ldapsiedn` parameter, which shows the location of the configuration data. For details, see Step 2 in the procedure below.

If the configuration data is under the DN `o=netscape.root`, follow all the steps in the procedure below.

If the configuration data is under the DN `o=comms-config`, you can use standard Directory Server methods and tools to migrate the data.

▼ To Transfer Messaging Server Configuration Data to a New Directory Server

The following migration steps are generic and conceptual. Your particular deployment may require modifications.

- 1 **Install the new Directory Server, if you have not already done so.**
- 2 **Find the location of the Messaging Server configuration data from the old Directory Server.**

The configuration parameters are stored under the DN defined by the `local.ldapsiedn` parameter in the `msg.conf` configuration file. Determine the value of `local.ldapsiedn` by running the `configutil` utility. This value is depicted in Figure 1.

Figure 1. Location of Messaging Server Configuration Data on Old Server

```
o=NetscapeRoot
  ou=AdminDomain
    cn=lion.varrius.org
      cn=Server Group
        cn=Sun ONE Messaging Suite
          cn=msg-config
            Configuration Data --> { . . . }
```

Example:

```
dn: cn=msg-sesta, cn=iplanet messaging suite, cn=Server Group,
cn=messaging1.siroe.com, ou=AdminDomain, o=netscapeRoot
```

Note – For Messaging Server 6.0 (Sun ONE Messaging Server) and later versions, the configuration information may be located under the root suffix `o=comms-config` instead of under `o=NetscapeRoot`.

If your `ldapsiedn` is located under `o=comms-config`, you can follow the normal migration procedures using the Directory Server migration tools.

- 3 **Extract the Messaging Server configuration data from the original (source) Directory Server.**

- a. **Put the configuration data into an LDIF file:**

```
/path-to-slapd-instance/db2ldif -s o=NetscapeRoot > /var/tmp/nsroot.ldif
```

b. Unfold the wrapped lines in the `nsroot.ldif` file.

The `ldapsearch` command wraps lines at 78 characters. Unwrap the lines and replace the `server_group_name` using the utility shown in Code Example 1. Save the output to a file—for example, `mods.ldif`.

Code Example 1. Unwrap Lines

```
#!/usr/bin/perl

$USAGE      = "Usage: $0 your_ldif_input_file [ldif_output_file]\n";
$input_file = shift || die $USAGE ;
$output_file = shift || ?-?;      # write to STDOUT by default

local $/ = ""; # set the record separator to paragraph mode

open(OUTFH, ">$output_file")
    || abort("ERROR: Unable to open $output_file for writing");

open(LDIFFILE, "$input_file")
    || abort("ERROR: Unable to open $input_file for reading ");

while (defined( $_ = <LDIFFILE>)) {
    s/\n //g;                                # unfold the lines
    next unless ( $_ =~ /o=NetscapeRoot\n/); # skip unless o=netscaperoot
    next if (s/slapd-//g);                    # skip slapd entries
    s/\nunique member: cn=Netscape Directory Server//g; # rm this unique member
    next if (s/Netscape Directory Server//g); # skip Dir Server entries
    print OUTFH "$_";                         # print to the output file
}
close (LDIFFILE);
close (OUTFH);
undef $/;
```

If you save the above perl code as `unwrap.pl`, you can run it as follows:

```
perl unwrap.pl /var/tmp/file.ldif /var/tmp/mod.ldif
```

4 Add the updated schema on the newly installed Directory Server.

Obtain the `comm_dssetup.pl` utility and install it on the newly installed Directory Server.

This utility is generally found as the package `SUNWcomds`. You can find it in the distribution that includes Directory Server or the distribution that contains Messaging Server.

Run `perl comm_dssetup.pl` against the newly installed Directory Server. (Make sure that the new Directory Server is running.)

5 Import the Messaging Server configuration data into the newly installed Directory Server.**a. Transfer the file `mods.ldif` onto the machine that hosts the new Directory Server.**

- b. To add the new information to the new Directory Server, run the following command:

```
ldapmodify -a -c -f mods.ldif
```

6 Transfer the other directory data into the new Directory Server.

- If you are upgrading your Directory Server, run the `migrateInstance` utility provided with the new Directory Server.
- If you are not upgrading your Directory Server, or if you want to use another data-migration method, use that method now to transfer the data.
- If you are migrating a user/group and PAB directory, transfer the user/group and PAB data from the old Directory Server to the new one.

Migrating user/group and PAB data to the new Directory Server is a simple task. Take the user/group and PAB LDIF data from the old Directory Server and load it into the new Directory Server.

7 Start Messaging Server.

```
path-to-startupscript/start-msg ha
```

Documentation, Support, and Training

The Sun web site provides information about the following additional resources:

- Documentation (<http://www.sun.com/documentation/>)
- Support (<http://www.sun.com/support/>)
- Training (<http://www.sun.com/training/>)

Third-Party Web Site References

Third-party URLs are referenced in this document and provide additional, related information.

Note – Sun is not responsible for the availability of third-party web sites mentioned in this document. Sun does not endorse and is not responsible or liable for any content, advertising, products, or other materials that are available on or through such sites or resources. Sun will not be responsible or liable for any actual or alleged damage or loss caused or alleged to be caused by or in connection with use of or reliance on any such content, goods, or services that are available on or through such sites or resources.

Sun Welcomes Your Comments

Sun is interested in improving its documentation and welcomes your comments and suggestions. To share your comments, go to <http://docs.sun.com> and click Send Comments. In the online form, provide the full document title and part number. The part number is a 7-digit or 9-digit number that can be found on the book's title page or in the document's URL. For example, the part number of this book is 819-6839-11.

