

System Administration Guide: Oracle® Solaris 8 Containers

Copyright © 2008, 2012, Oracle and/or its affiliates. All rights reserved.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Ce logiciel et la documentation qui l'accompagne sont protégés par les lois sur la propriété intellectuelle. Ils sont concédés sous licence et soumis à des restrictions d'utilisation et de divulgation. Sauf disposition de votre contrat de licence ou de la loi, vous ne pouvez pas copier, reproduire, traduire, diffuser, modifier, breveter, transmettre, distribuer, exposer, exécuter, publier ou afficher le logiciel, même partiellement, sous quelque forme et par quelque procédé que ce soit. Par ailleurs, il est interdit de procéder à toute ingénierie inverse du logiciel, de le désassembler ou de le décompiler, excepté à des fins d'interopérabilité avec des logiciels tiers ou tel que prescrit par la loi.

Les informations fournies dans ce document sont susceptibles de modification sans préavis. Par ailleurs, Oracle Corporation ne garantit pas qu'elles soient exemptes d'erreurs et vous invite, le cas échéant, à lui en faire part par écrit.

Si ce logiciel, ou la documentation qui l'accompagne, est concédé sous licence au Gouvernement des Etats-Unis, ou à toute entité qui délivre la licence de ce logiciel ou l'utilise pour le compte du Gouvernement des Etats-Unis, la notice suivante s'applique:

U.S. GOVERNMENT END USERS. Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

Ce logiciel ou matériel a été développé pour un usage général dans le cadre d'applications de gestion des informations. Ce logiciel ou matériel n'est pas conçu ni n'est destiné à être utilisé dans des applications à risque, notamment dans des applications pouvant causer des dommages corporels. Si vous utilisez ce logiciel ou matériel dans le cadre d'applications dangereuses, il est de votre responsabilité de prendre toutes les mesures de secours, de sauvegarde, de redondance et autres mesures nécessaires à son utilisation dans des conditions optimales de sécurité. Oracle Corporation et ses affiliés déclinent toute responsabilité quant aux dommages causés par l'utilisation de ce logiciel ou matériel pour ce type d'applications.

Oracle et Java sont des marques déposées d'Oracle Corporation et/ou de ses affiliés. Tout autre nom mentionné peut correspondre à des marques appartenant à d'autres propriétaires qu'Oracle.

Intel et Intel Xeon sont des marques ou des marques déposées d'Intel Corporation. Toutes les marques SPARC sont utilisées sous licence et sont des marques ou des marques déposées de SPARC International, Inc. AMD, Opteron, le logo AMD et le logo AMD Opteron sont des marques ou des marques déposées d'Advanced Micro Devices. UNIX est une marque déposée d'The Open Group.

Ce logiciel ou matériel et la documentation qui l'accompagne peuvent fournir des informations ou des liens donnant accès à des contenus, des produits et des services émanant de tiers. Oracle Corporation et ses affiliés déclinent toute responsabilité ou garantie expresse quant aux contenus, produits ou services émanant de tiers. En aucun cas, Oracle Corporation et ses affiliés ne sauraient être tenus pour responsables des pertes subies, des coûts occasionnés ou des dommages causés par l'accès à des contenus, produits ou services tiers, ou à leur utilisation.

Contents

Preface	7
1 Introduction to Solaris 8 Containers	11
About Branded Zones	11
Components Defined by the Brand	12
Processes Running in a Branded Zone	12
General Zones Characteristics	13
General Zones Concepts	13
About Oracle Solaris 8 Branded Zones	14
Oracle Solaris 10 Features Available to Zones	14
Limitations	14
Using ZFS	15
Adding Components	15
Ability to Directly Migrate Installed Systems Into Zones	16
2 Obtaining and Installing the Software	17
Software Download	17
Solaris 8 Containers Versions and System Requirements	17
Oracle Solaris 10 Patch Requirements and Compatibility if Running a Prior Release	19
▼ Installing the Solaris 8 Containers 1.0.1 Software on the Oracle Solaris 10 Host System	19
▼ Installing the Solaris 8 Containers 1.0 Software on the Solaris 10 Host System	20
3 Assessing a Solaris 8 System and Creating an Archive	23
Assess the Solaris 8 System	23
Creating the Image for Directly Migrating Solaris 8 Systems Into Zones	24
▼ How to Use <code>flarcreate</code> to Create the Image	24
Other Archive Creation Methods	25

Host ID Emulation	25
Setting the Machine Name to sun4u	25
4 Configuring a solaris8 Zone	27
Preconfiguration Tasks	27
solaris8 Branded Zone Configuration Process	28
Resources Included in the Configuration by Default	28
File Systems Defined in solaris8 Branded Zones	28
Privileges Defined in solaris8 Branded Zones	28
Configure the solaris8 Zone	29
▼ How to Configure a solaris8 Branded Zone	29
5 Installing the solaris8 Zone	33
The zoneadm Command	33
Migration Process	33
solaris8 Zone Installation Images	34
▼ How to Install the Zone	34
6 Booting a Zone and Zone Migration	37
About Booting the Zone	37
▼ How to Boot the Zone	37
Migrating a solaris8 Zone to Another Host	38
About Detaching and Attaching the Zone	38
Zone Migration and Initial Boot	38
7 About Zone Login and Post-Installation Configuration	39
Internal Zone Configuration	39
▼ How to Log In to the Zone Console to Complete System Identification	39
Applying Solaris 8 Patches in the Container	41
Tuning /etc/system and Using Resource Controls	41
Modifying /etc/system	42
Using zonecfg to Set Resource Controls	43
Running X11 Applications in a solaris8 Branded Zone	43
▼ How to Use ssh X11 Forwarding	43

8 Troubleshooting Miscellaneous Solaris 8 Branded Zones Problems	45
Library Version Affecting Application Behavior	45
A solaris8(5) Man Page	47
NAME	47
Description	47
Configuration and Administration	47
Application Support	48
Zone Migration	48
Attributes	49
See Also	49
Index	51

Preface

This guide covers the Oracle Solaris Legacy Containers product features Oracle Solaris 8 Containers 1.0.1 and Oracle Solaris 8 Containers 1.0 products for SPARC machines. To use either version, you must install the correct Oracle Solaris 10 release, as described in this document, and set up any networking software that you plan to use.

Related Companion Book

For additional information not in this guide, also refer to the *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*. That book provides a complete overview of zones and branded zones. See “General Zones Concepts” on page 13 for specific topics you might need to review.

Who Should Use This Book

This book is intended for anyone responsible for administering one or more systems that run the Solaris 10 release. To use this book, you should have at least 1 to 2 years of UNIX system administration experience.

How the System Administration Volumes Are Organized

Here is a list of the topics that are covered by the volumes of the System Administration Guides.

Book Title	Topics
<i>System Administration Guide: Basic Administration</i>	User accounts and groups, server and client support, shutting down and booting a system, managing services, and managing software (packages and patches)
<i>System Administration Guide: Advanced Administration</i>	Printing services, terminals and modems, system resources (disk quotas, accounting, and crontabs), system processes, and troubleshooting Solaris software problems
<i>System Administration Guide: Devices and File Systems</i>	Removable media, disks and devices, file systems, and backing up and restoring data

Book Title	Topics
<i>System Administration Guide: IP Services</i>	TCP/IP network administration, IPv4 and IPv6 address administration, DHCP, IPsec, IKE, IP filter, Mobile IP, IP network multipathing (IPMP), and IPQoS
<i>System Administration Guide: Naming and Directory Services (DNS, NIS, and LDAP)</i>	DNS, NIS, and LDAP naming and directory services, including transitioning from NIS to LDAP and transitioning from NIS+ to LDAP
<i>System Administration Guide: Naming and Directory Services (NIS+)</i>	NIS+ naming and directory services
<i>System Administration Guide: Network Services</i>	Web cache servers, time-related services, network file systems (NFS and Autofs), mail, SLP, and PPP
<i>System Administration Guide: Security Services</i>	Auditing, device management, file security, BART, Kerberos services, PAM, Solaris cryptographic framework, privileges, RBAC, SASL, and Solaris Secure Shell
<i>System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones</i>	Resource management topics projects and tasks, extended accounting, resource controls, fair share scheduler (FSS), physical memory control using the resource capping daemon (rcapd), and resource pools; virtualization using Oracle Solaris Zones software partitioning technology
<i>Oracle Solaris ZFS Administration Guide</i>	ZFS storage pool and file system creation and management, snapshots, clones, backups, using access control lists (ACLs) to protect ZFS files, using Oracle Solaris ZFS on a Solaris system with zones installed, emulated volumes, and troubleshooting and data recovery

Related Third-Party Web Site References

Third-party URLs are referenced in this document and provide additional, related information.

Note – Oracle is not responsible for the availability of third-party web sites mentioned in this document. Oracle does not endorse and is not responsible or liable for any content, advertising, products, or other materials that are available on or through such sites or resources. Sun will not be responsible or liable for any actual or alleged damage or loss caused or alleged to be caused by or in connection with use of or reliance on any such content, goods, or services that are available on or through such sites or resources.

Documentation, Support, and Training

See the following web sites for additional resources:

- Documentation (<http://www.oracle.com/technetwork/documentation/>)
- Support (<http://www.oracle.com/us/support/systems/index.html>)
- Training (<http://education.oracle.com>)

Oracle Welcomes Your Comments

Oracle welcomes your comments and suggestions on the quality and usefulness of its documentation. If you find any errors or have any other suggestions for improvement, click Feedback.

Oracle Technology Network (<http://www.oracle.com/technetwork/index.html>) offers a range of resources related to Oracle software:

- Discuss technical problems and solutions on the [Discussion Forums](http://forums.oracle.com) (<http://forums.oracle.com>).
- Get hands-on step-by-step tutorials with [Oracle By Example](http://www.oracle.com/technetwork/tutorials/index.html) (<http://www.oracle.com/technetwork/tutorials/index.html>).

Typographic Conventions

The following table describes the typographic conventions that are used in this book.

TABLE P-1 Typographic Conventions

Typeface	Meaning	Example
AaBbCc123	The names of commands, files, and directories, and onscreen computer output	Edit your <code>.login</code> file. Use <code>ls -a</code> to list all files. <code>machine_name% you have mail.</code>
AaBbCc123	What you type, contrasted with onscreen computer output	<code>machine_name% su</code> Password:
<i>aabbcc123</i>	Placeholder: replace with a real name or value	The command to remove a file is <code>rm filename</code> .

TABLE P-1 Typographic Conventions (Continued)

Typeface	Meaning	Example
<i>AaBbCc123</i>	Book titles, new terms, and terms to be emphasized	Read Chapter 6 in the <i>User's Guide</i> . <i>A cache</i> is a copy that is stored locally. Do <i>not</i> save the file. Note: Some emphasized items appear bold online.

Shell Prompts in Command Examples

The following table shows the default UNIX system prompt and superuser prompt for shells that are included in the Oracle Solaris OS. Note that the default system prompt that is displayed in command examples varies, depending on the Oracle Solaris release.

TABLE P-2 Shell Prompts

Shell	Prompt
Bash shell, Korn shell, and Bourne shell	\$
Bash shell, Korn shell, and Bourne shell for superuser	#
C shell	machine_name%
C shell for superuser	machine_name#

Introduction to Solaris 8 Containers

The branded zones framework is used to create non-global zones that contain non-native operating environments. These containers are branded zones used in the Oracle Solaris Operating System to run applications that cannot be run in a native environment. The brand described here is the `solaris8` brand, Solaris 8 Containers.

Note – If you want to create `solaris8` zones now, go to [“Assess the Solaris 8 System”](#) on page 23.

About Branded Zones

By default, a non-global zone has the same characteristics as operating system in the global zone, which is running the Oracle Solaris 10 Operating System or later Oracle Solaris 10 release. These *native* non-global zones and the global zone share their conformance to standards, runtime behavior, command sets, and performance traits in common.

It is also possible to run a different operating environment inside of a non-global zone. The branded zone (BrandZ) framework extends the Solaris Zones infrastructure to include the creation of brands, or alternative sets of runtime behaviors. *Brand* can refer to a wide range of operating environments. For example, the non-global zone can emulate another version of the Solaris Operating System, or an operating environment such as Linux. Or, it might augment the native brand behaviors with additional characteristics or features. Every zone is configured with an associated brand.

The brand defines the operating environment that can be installed in the zone and determines how the system will behave within the zone so that the non-native software installed in the zone functions correctly. In addition, a zone's brand is used to identify the correct application type at application launch time. All branded zone management is performed through extensions to the native zones structure. Most administration procedures are identical for all zones.

You can change the brand of a zone in the *configured* state. Once a branded zone has been *installed*, the brand cannot be changed or removed.

BrandZ extends the zones tools in the following ways:

- The `zonecfg` command is used to set a zone's brand type when the zone is configured.
- The `zoneadm` command is used to report a zone's brand type as well as administer the zone.

Note – Although you can configure and install branded zones on an Oracle Solaris Trusted Extensions system that has labels enabled, you cannot boot branded zones on this system configuration.

Components Defined by the Brand

The following components available in a branded zone are defined by the brand.

- The privileges.
- Device support. A brand can choose to disallow the addition of any unsupported or unrecognized devices. Devices can be added to `solaris8` non-global zones. See [“About Oracle Solaris 8 Branded Zones” on page 14](#).
- The file systems required for a branded zone are defined by the brand. You can add additional Solaris file systems to a branded zone by using the `fs` resource property of `zonecfg`.

Processes Running in a Branded Zone

Branded zones provide a set of interposition points in the kernel that are only applied to processes executing in a branded zone.

- These points are found in such paths as the `syscall` path, the process loading path, and the thread creation path.
- At each of these points, a brand can choose to supplement or replace the standard Solaris behavior.

A brand can also provide a plug-in library for `librtld_db`. The plug-in library allows Solaris tools such as the debugger, described in [`mdb\(1\)`](#), and DTrace, described in [`dttrace\(1M\)`](#), to access the symbol information of processes running inside a branded zone.

General Zones Characteristics

The container provides a virtual mapping from the application to the platform resources. Zones allow application components to be isolated from one another even though the zones share a single instance of the Solaris Operating System. Resource management features permit you to allocate the quantity of resources that a workload receives.

The container establishes boundaries for resource consumption, such as CPU utilization. These boundaries can be expanded to adapt to changing processing requirements of the application running in the container.

General Zones Concepts

For additional information not in this guide, also refer to the *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*. That book provides a complete overview of Solaris Zones and branded zones.

You should be familiar with the following zones and resource management concepts, which are discussed in the guide:

- Supported and unsupported features
- Resource controls that enable the administrator to control how applications use available system resources
- Commands used to configure, install, and administer zones, primarily `zonecfg`, `zoneadm`, and `zlogin`
- The global zone and the non-global zone
- The whole-root non-global zone model
- The global administrator and the zone administrator
- The zone state model
- The zone isolation characteristics
- Privileges
- Networking
- Zone IP types, exclusive-IP and shared-IP
- The Solaris Container concept, which is the use of resource management features, such as resource pools, with zones
- The fair share scheduler (FSS), a scheduling class that enables you to allocate CPU time based on shares
- The resource capping daemon (`rcapd`), which can be used from the global zone to control resident set size (RSS) usage of branded zones

About Oracle Solaris 8 Branded Zones

A Solaris 8 branded zone (`solaris8`) is a complete runtime environment for Solaris 8 applications on SPARC machines running the Oracle Solaris 10 8/07 Operating System or later. The brand supports the execution of 32-bit and 64-bit Solaris 8 applications.

`solaris8` branded zones are based on the whole root zone model. Each zone's file system contains a complete copy of the software that comprises the operating system. However, `solaris8` zones are different from native whole root zones in that central patching is not applied.

Oracle Solaris 10 Features Available to Zones

Many Oracle Solaris 10 capabilities are available to the `solaris8` zones, including the following:

- Fault management architecture (FMA) for better system reliability (see [smf\(5\)](#)).
- The ability to run on newer hardware that Solaris 8 does not support.
- Oracle Solaris 10 performance improvements.
- DTrace, run from the global zone, can be used to examine processes in `solaris8` zones.
- Auditing is supported in `solaris8` and `solaris9` containers. For this support, auditing should be enabled in the global zone. Per-zone auditing policy is not supported for `solaris8` and `solaris9` containers. For more information, see [“Using Oracle Solaris Auditing in Zones” in System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones](#).

Limitations

Some functionality available in Solaris 8 is not available inside of zones.

General Non-Global Zone Limitations

The following features cannot be configured in a non-global zone on the Oracle Solaris 10 release:

- Solaris Volume Manager metadevices
- DHCP address assignment in a shared-IP zone
- SSL proxy server

In addition, a non-global zone cannot be an NFS server, and dynamic reconfiguration (DR) operations can only be done from the global zone.

Limitations Specific to solaris8 Branded Zones

The following limitations apply to solaris8 branded zones:

- The CPU performance counter facility described in [cpc\(3CPC\)](#) is not available.
- The following disk and hardware related commands do not work:
 - `add_drv(1M)`
 - `disks(1M)`
 - `format(1M)`
 - `fdisk(1M)`
 - `prtdiag(1M)`
 - `rem_drv(1M)`

Using ZFS

Although the zone cannot use a delegated ZFS dataset, the zone can reside on a ZFS file system. You can add a ZFS file system to share with the global zone through the `zonecfg fs` resource. See Step 7 in [“How to Configure a solaris8 Branded Zone”](#) on page 29.

Note that the `setfacl` and `getfacl` commands cannot be used with ZFS. When a `cpio` or a `tar` archive with ACLs set on the files is unpacked, the archive will receive warnings about not being able to set the ACLs, although the files will be unpacked successfully. These commands can be used with UFS.

Adding Components

You can add the following components to a solaris8 branded zone through the `zonecfg` command:


- You can add additional Solaris file systems to a branded zone by using the `fs` resource. For examples, see [“How to Configure the Zone”](#) in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*.
- Devices can be added to a solaris8 non-global zone by using the `device` resource. For information about adding devices, see Chapter 18, [“Planning and Configuring Non-Global Zones \(Tasks\)”](#), in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*. To learn more about device considerations in non-global zones, see [“Device Use in Non-Global Zones”](#) in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*.
- Privileges can be added to a solaris8 non-global zone by using the `limitpriv` resource. For information about adding privileges, see Chapter 18, [“Planning and Configuring Non-Global Zones \(Tasks\)”](#), in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones* [“Privileges in a Non-Global Zone”](#) in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*.

- You can specify network configurations. For more information, see “Preconfiguration Tasks” on page 27, “Networking in Shared-IP Non-Global Zones” in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones* and “Oracle Solaris 10 8/07: Networking in Exclusive-IP Non-Global Zones” in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*
- You can use various resource control features. For more information, see Chapter 17, “Non-Global Zone Configuration (Overview),” in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*, Chapter 18, “Planning and Configuring Non-Global Zones (Tasks),” in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*, and Chapter 27, “Oracle Solaris Zones Administration (Overview),” in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*.

Ability to Directly Migrate Installed Systems Into Zones

An existing Solaris 8 system can be directly migrated into a `solaris8` branded zone. It is best if the system is running the Solaris 8 2/04 release. For more information, see “Creating the Image for Directly Migrating Solaris 8 Systems Into Zones” on page 24.

FIGURE 1-1 Solaris 8 System Migrated Into a solaris8 Zone



Obtaining and Installing the Software

This chapter discusses the following topics:

- The product versions available for download and associated system requirements
- How to download the media to the Oracle Solaris 10 host and install the Solaris 8 Containers product.

Software Download

Instructions for downloading the Solaris 8 Containers product are available at the [Oracle Software Delivery Cloud \(https://edelivery.oracle.com\)](https://edelivery.oracle.com).

The software download site for patches is [My Oracle Support \(https://support.oracle.com\)](https://support.oracle.com). Click on the "Patches & Updates" tab. On that site, you can view the download instructions and download the images. Contact your support provider for additional information regarding patches.

Solaris 8 Containers Versions and System Requirements

The Oracle Solaris 8 Containers software can be installed on a SPARC system running at least the Oracle Solaris 10 8/07 release.

Container Version	Obtaining Required Packages
Solaris 8 Containers 1.0.1	The SUNWs8brandr and SUNWs8brandu packages are installed as part of an Oracle Solaris 10 installation. The SUNWs8brandk package is only available from Oracle Software Delivery Cloud with a signed license agreement.

Container Version	Obtaining Required Packages
Solaris 8 Containers 1.0	The SUNWs8brandr and SUNWs8brandu packages are only available from Oracle Software Delivery Cloud with a signed license agreement. The SUNWs8brandk package is not required for this version.

The product media contains the following versions:

- Oracle Solaris 8 Containers 1.0.1, for systems running:
 - Oracle Solaris 10 10/08 or later
 - Kernels 137137-07 or later

Systems running Solaris 8 Containers 1.0 (or Solaris 8 Migration Assistant) also must install the 1.0.1 product if the systems are updated to:

- Oracle Solaris 10 10/08 or later
- Kernels 137137-07 or later

SUNWs8brandr and SUNWs8brandu are installed as part of an Oracle Solaris 10 installation.

SUNWs8brandk is only available from [Oracle Software Delivery Cloud](#). To obtain the package:

1. Go to the [Oracle Software Delivery Cloud](#).
 2. Click Sign In/Register to access export validation.
 3. Complete the Export Validation license agreement.
 4. Select product: "Oracle Solaris" and platform "Oracle Solaris on SPARC (64-bit)," and click search.
 5. Select Oracle Solaris Legacy Containers to download the package.
 6. Install the package on your system.
- Oracle Solaris 8 Containers 1.0, which is only available from Oracle Software Delivery Cloud, is for systems running:
 - Oracle Solaris 10 8/07, with required Solaris patch 127111-01 or later applied
 - Oracle Solaris 10 5/08
 - Kernels 127111 (all versions)
 - Kernels 127127 (all versions)
 - Kernels 137111 (all versions)

The packages in the Oracle Solaris 8 Containers 1.0 media have been updated to include the latest functionality in Oracle Solaris 8 Containers patch 128548-08.

The product download also includes a README file containing installation instructions for both versions, and a sample Solaris 8 flash archive image provided for validation purposes.

Oracle Solaris 10 Patch Requirements and Compatibility if Running a Prior Release

The 128548-02 patch allows earlier versions of the Solaris 8 Container product, called Solaris 8 Migration Assistant 1.0, to be run on Solaris 10 8/07 with 127111-01 and all subsequent kernel patches and Solaris 10 updates. *All users are required to install the patch or a later revision, if available, to have a supportable configuration.*

The patch can be found on [My Oracle Support \(https://support.oracle.com\)](https://support.oracle.com).

If the patch is *not* installed, the product is only supported on the following set of Solaris 10 patches:

- 127111-01 SunOS 5.10: kernel patch
- 127111-02 SunOS 5.10: kernel patch
- 127111-03 SunOS 5.10: kernel patch

▼ Installing the Solaris 8 Containers 1.0.1 Software on the Oracle Solaris 10 Host System

The `SUNWs8brandr` and `SUNWs8brandu` packages should be installed on your system during the Solaris system installation. If not already installed, the packages are available from the Solaris 10 10/08 media. See step 3.

- 1 **Become superuser, or assume the Primary Administrator role.**
- 2 **Install the Solaris 10 10/08 release on the target system. See the [Solaris 10 10/08 Release and Installation library \(http://download.oracle.com/docs/cd/E19253-01/index.html\)](http://download.oracle.com/docs/cd/E19253-01/index.html).**
- 3 **If not already present on the system, install the packages `SUNWs8brandr` and `SUNWs8brandu` in the following order.**

```
# pkgadd -d /path/to/media SUNWs8brandr
...
Installation of <SUNWs8brandr> was successful.
# pkgadd -d /path/to/media SUNWs8brandu
...
Installation of <SUNWs8brandu> was successful.
```

These packages are available from the Oracle Solaris 10 10/08 media.

- 4 **Install the package `SUNWs8brandk`.**
- ```
pkgadd -d /path/to/media/solarislegacycontainers/1.0.1/Product SUNWs8brandk
...
Installation of <SUNWs8brandk> was successful.
```

The package is available for download from [the Oracle Software Delivery Cloud](#) for the Solaris 8 Containers 1.0.1 product.

- 5 (Optional) If you plan to install the zone by using the sample `soLarIs8` system image archive, `soLarIs8-image.flar`, the file is available for download from the Oracle Software Delivery Cloud for the Solaris 8 Containers 1.0.1 product. Copy the file either to the Solaris 10 system, or to an NFS server accessible to the system.

**See Also** For more information about installing patches and packages, see [Chapter 25, “About Packages and Patches on an Oracle Solaris System With Zones Installed \(Overview\)”](#), in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones* and [Chapter 26, “Adding and Removing Packages and Patches on an Oracle Solaris System With Zones Installed \(Tasks\)”](#), in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*.

Aspects of central patching covered in these chapters do not apply to `soLarIs8` branded zones.

## ▼ Installing the Solaris 8 Containers 1.0 Software on the Solaris 10 Host System

- 1 Become superuser, or assume the Primary Administrator role.
- 2 Install the Solaris 10 8/07 or Solaris 10 5/08 release on the target system. See the appropriate [Solaris 10 Release and Installation Collection on \(http://download.oracle.com/docs/cd/E19253-01/index.html\)](http://download.oracle.com/docs/cd/E19253-01/index.html).
- 3 (Solaris 10 8/07 release only) Install the patch 127111-01 or later in the global zone and reboot. The patch is available from [My Oracle Support \(https://support.oracle.com\)](https://support.oracle.com).

```
global# patchadd 127111-01
```

To view the patch on the system, use:

```
patchadd -p | grep 127111-01
```

---

**Note** – See [“Oracle Solaris 10 Patch Requirements and Compatibility if Running a Prior Release” on page 19](#) for more information.

---

- 4 Install the packages `SUNWs8brandr` and `SUNWs8brandu` in the following order.  

```
pkgadd -d /path/to/media/solarislegacycontainers/1.0/Product SUNWs8brandr
...
Installation of <SUNWs8brandr> was successful.
pkgadd -d /path/to/media/solarislegacycontainers/1.0/Product SUNWs8brandu
```

...  
Installation of <SUNWs8brandu> was successful.

The packages are available for download from the Oracle Software Delivery Cloud for the Solaris 8 Containers 1.0.1 product.

- 5 (Optional) If you plan to install the zone by using the sample `soLarIs8` system image archive, `soLarIs8-image.flar`, the file is available for download from Oracle Software Delivery Cloud for the Solaris 8 Containers 1.0.1 product. Copy the file either to the Solaris 10 system, or to an NFS server accessible to the system.**

**See Also** For more information about installing patches and packages, see [Chapter 25, “About Packages and Patches on an Oracle Solaris System With Zones Installed \(Overview\)”](#), in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones* and [Chapter 26, “Adding and Removing Packages and Patches on an Oracle Solaris System With Zones Installed \(Tasks\)”](#), in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*.

Aspects of central patching covered in these chapters do not apply to `soLarIs8` branded zones.



# Assessing a Solaris 8 System and Creating an Archive

---

This chapter discusses acquiring information about the Solaris 8 system and creating the archive of the Solaris 8 system.

## Assess the Solaris 8 System

Examine the source system and collect needed information.

- Obtain the hostname:

```
hostname
```

- Obtain the host ID:

```
hostid
```

Also see “[Host ID Emulation](#)” on page 25.

- Obtain the RPC domainname:

```
domainname
```

- Obtain the root password.

- View the software being run on the system:

```
ps -ef
```

- Check the networking utilized on the system:

```
ifconfig -a
```

- View the storage utilized, for example, by viewing the contents of `/etc/vfstab`.

- View the amount of local disk storage in use, which determines the size of the archive:

```
df -k
```

- Determine the patches that are on the system:

```
patchadd -p
```

- Examine the contents of `/etc/system`.

# Creating the Image for Directly Migrating Solaris 8 Systems Into Zones

You can use the Flash Archiving tools to create an image of an installed Solaris 8 2/04 system that can be migrated into a zone. If your Solaris 8 system is patched to the latest recommended list and the `SUNwinst` package is installed, you already have these tools installed.

The image can be fully configured with all of the software that will be run in the zone. This image is used by the installer when the zone is installed.

See [Example 5-1](#) for information on the installer.

## ▼ How to Use `flarcreate` to Create the Image

Use this process to create the Solaris 8 2/04 or later system image. This example procedure uses NFS to place the flash archive on the target Solaris 10 system, but you could use any method to move the files.

You must be the global administrator in the global zone to perform this procedure.

- 1 **Become superuser, or assume the Primary Administrator role.**
- 2 **Log into the Solaris 8 2/04 or later system to archive.**
- 3 **Change directories to the root directory.**
- 4 **Use `flarcreate` to create a flash archive image file named `s8-system`, and place the archive onto the Solaris 10 system:**

```
cd /
```

```
s8-system # flarcreate -S -n s8-system /net/s10system/export/s8-system.flar
Determining which filesystems will be included in the archive...
Creating the archive...
cpio: File size of "etc/mnttab" has
increased by 435
2068650 blocks
1 error(s)
Archive creation complete.
```

---

**Tip** – In some cases, `flarcreate` can display errors from `cpio`. Most commonly, these are messages such as `File size of etc/mnttab has increased by 33`. When these messages pertain to log files or files that reflect system state, they can be ignored. Be sure to review all error messages thoroughly.

---

## Other Archive Creation Methods

You can use alternate methods for creating the archive. The installer can accept the following archive formats:

- `cpio` archives
- `gzip` compressed `cpio` archives
- `bzip2` compressed `cpio` archives
- `pax` archives created with the `-x xustar` (XUSTAR) format
- `ufsdump` level zero (full) backups

Additionally, the installer can accept a directory of files created by using an archiving utility that saves and restores file permissions, ownership, and links.

For more information, see the [cpio\(1\)](#), [pax\(1\)](#), [bzip2\(1\)](#), [gzip\(1\)](#), and [ufsdump\(1M\)](#) man pages.

## Host ID Emulation

When applications are migrated from a standalone Solaris 8 system into a `solaris8` zone on a new system, the `hostid` changes to be the `hostid` of the new machine.

In some cases, applications depend on the original `hostid`, and it is not possible to update the application configuration. In these cases, the `solaris8` zone can be configured to use the `hostid` of the original system. This is done by setting a `zonecfg` attribute to specify the `hostid`, as shown in “[How to Configure a solaris8 Branded Zone](#)” on page 29. The value used should be the output of the `hostid` command as run on the original system. To view the `hostid` in an installed zone, also use the `hostid` command.

For more information, see [hostid\(1\)](#).

## Setting the Machine Name to sun4u

A `zonecfg` attribute can be used to specify the machine name returned by `uname` as `sun4u`, even if the underlying Solaris 10 system is running on an `sun4v` machine. The setting is shown in “[How to Configure a solaris8 Branded Zone](#)” on page 29.

To use this attribute, you must have Solaris 8 Containers patch 128548-07 or higher installed.



# Configuring a solaris8 Zone

---

This chapter discusses configuring the solaris8 branded zone.

## Preconfiguration Tasks

You will need the following:

- A SPARC based system running Solaris 10 8/07 or later update release. All SPARC systems capable of running Solaris 10 are supported.
- For zones that require network connectivity, you will need to provide the following information when you create the zone configuration.
  - For a shared-IP zone, you will need one or more unique IPv4 addresses for each zone you want to create. You must also specify the physical interface.
  - For an exclusive-IP zone, you must set the `ip-type` property to `exclusive`. You must also assign a data-link using the `physical` property of the `net` resource. The zone requires exclusive access to one or more network interfaces. The interface could be a separate LAN such as `bge1`, or a separate VLAN such as `bge2000`. The data-link must be of the `GLDv3` type. For more information on `GLDv3` interfaces, see “[Oracle Solaris Interface Types](#)” in *System Administration Guide: IP Services*. Note that the address property of the `net` resource is not set in an exclusive-IP zone.

---

**Note** – Exclusive-IP zones are a new feature in the Solaris 10 8/07 release. If you are not familiar with this feature, see the *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones* for more information.

---

- (Optional) A SPARC based machine running the Solaris 8 operating system that you want to migrate into a solaris8 container. You can generate your own images from existing systems. The process is described in “[Creating the Image for Directly Migrating Solaris 8 Systems Into Zones](#)” on page 24.

A sample Solaris 8 based image that can be used to create a `solaris8` container is also available. See Step 5 of “[Installing the Solaris 8 Containers 1.0 Software on the Solaris 10 Host System](#)” on page 20.

## solaris8 Branded Zone Configuration Process

The `zonecfg` command is used to do the following:

- Set the brand for the zone.
- Create the configuration for the `solaris8` zone. Refer to the information you gathered in “[Assess the Solaris 8 System](#)” on page 23.
- Verify the configuration to determine whether the specified resources and properties are allowed and internally consistent on a hypothetical SPARC based system.
- Perform a brand-specific verification. The verification ensures that the zone does not have any inherited package directories or ZFS datasets.

The check performed by the `zonecfg verify` command for a given configuration verifies the following:

- Ensures that a zone path is specified
- Ensures that all of the required properties for each resource are specified
- Ensures that brand requirements are met

For more information about the `zonecfg` command, see the [zonecfg\(1M\)](#) man page.

## Resources Included in the Configuration by Default

### File Systems Defined in solaris8 Branded Zones

The file systems that are required for a branded zone are defined in the brand. You can add additional Solaris file systems to a `solaris8` branded zone by using the `fs` resource property.

### Privileges Defined in solaris8 Branded Zones

Processes are restricted to a subset of privileges. Privilege restriction prevents a zone from performing operations that might affect other zones. The set of privileges limits the capabilities of privileged users within the zone.

Default, required default, optional, and prohibited privileges are defined by each brand. You can also add or remove certain privileges by using the `limitpriv` property. See “[Privileges in a](#)

Non-Global Zone” in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones* for information on Solaris privileges with respect to zones.

For more information about privileges, see the `ppriv(1)` man page and *System Administration Guide: Security Services*.

## Configure the solaris8 Zone

You must be the global administrator in the global zone to perform these procedures.

### ▼ How to Configure a solaris8 Branded Zone

Use the `zonecfg` command to create an s8 zone.

You must be the global administrator in the global zone to perform this procedure.

The `zonecfg` prompt is of the following form:

```
zonecfg:zonename>
```

When you are configuring a specific resource type, such as a file system, that resource type is also included in the prompt:

```
zonecfg:zonename: fs>
```

---

**Note** – Resource controls are set to the Solaris 8 defaults. Review these settings to see whether they should be adjusted.

---

---

**Tip** – If you know you will be using CDs or DVDs to install applications in a solaris8 branded zone, use `add fs` to add read-only access to CD or DVD media in the global zone when you initially configure the branded zone. A CD or DVD can then be used to install a product in the branded zone. See “How to Add Access to CD or DVD Media in a Non-Global Zone” in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones* for more information.

---

This procedure describes configuring a shared-IP zone. To configure an exclusive-IP zone, see “Resource Type Properties” in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*.

#### 1 Become superuser, or assume the Primary Administrator role.

**2 Set up a shared-IP zone configuration with the zone name you have chosen.**

The name `s8-zone` is used in this example procedure.

```
global# zonecfg -z s8-zone
```

If this is the first time you have configured this zone, you will see the following system message:

```
s8-zone: No such zone configured
Use 'create' to begin configuring a new zone.
```

**3 Create the new solaris8 zone configuration by using the SUNWsolaris8 template.**

```
zonecfg:s8-zone> create -t SUNWsolaris8
```

**4 Set the zone path, `/export/home/s8-zone` in this procedure.**

```
zonecfg:s8-zone> set zonepath=/export/home/s8-zone
```

**5 Set the autoboot value.**

If set to `true`, the zone is automatically booted when the global zone is booted. Note that for the zones to autoboot, the zones service `svc:/system/zones:default` must also be enabled. The default value is `false`.

```
zonecfg:s8-zone> set autoboot=true
```

**6 Add a network virtual interface.**

```
zonecfg:s8-zone> add net
```

**a. Set the IP address. In this procedure, `10.6.10.233` is used.**

```
zonecfg:s8-zone:net> set address=10.6.10.233
```

**b. Set the physical device type for the network interface, the `bge` device in this procedure.**

```
zonecfg:s8-zone:net> set physical=bge0
```

**c. End the specification.**

```
zonecfg:s8-zone:net> end
```

This step can be performed more than once to add more than one network interface.

**7 Add a ZFS file system shared with the global zone.**

```
zonecfg:s8-zone> add fs
```

**a. Set the type to `zfs`.**

```
zonecfg:s8-zone:fs> set type=zfs
```

**b. Set the directory to mount from the global zone.**

```
zonecfg:s8-zone:fs> set special=share/zone/s8-zone
```

**c. Specify the mount point.**

```
zonecfg:s8-zone:fs> set dir=/export/shared
```

**d. End the specification.**

```
zonecfg:s8-zone:fs> end
```

This step can be performed more than once to add more than one file system. Note that an `lofs` mount would be an alternative if the file system must be shared with the global zone.

**8 (Optional) Set the `hostid` to be the `hostid` of the source system.**

```
zonecfg:s8-zone> add attr
```

**a. Set the attribute name to `hostid`.**

```
zonecfg:s8-zone:attr> set name=hostid
```

**b. Set the type to `string`.**

```
zonecfg:s8-zone:attr> set type=string
```

**c. Set the value to the `hostid`.**

```
zonecfg:s8-zone:attr> set value=8325f14d
```

**d. End the specification.**

```
zonecfg:s8-zone:attr> end
```

**9 (Optional) Set the machine name returned by `uname` to always be `sun4u`.**

```
zonecfg:s8-zone> add attr
```

**a. Set the attribute name to `machine`.**

```
zonecfg:s8-zone:attr> set name=machine
```

**b. Set the type to `string`.**

```
zonecfg:s8-zone:attr> set type=string
```

**c. Set the value to `sun4u`.**

```
zonecfg:s8-zone:attr> set value=sun4u
```

**d. End the specification.**

```
zonecfg:s8-zone:attr> end
```

**10 Verify the zone configuration for the zone.**

```
zonecfg:s8-zone> verify
```

**11 Commit the zone configuration for the zone.**

```
zonecfg:s8-zone> commit
```

**12 Exit the zonecfg command.**

```
zonecfg:s8-zone> exit
```

Note that even if you did not explicitly type `commit` at the prompt, a `commit` is automatically attempted when you type `exit` or an EOF occurs.

**13 Use the info subcommand to check that the brand is set to solaris8.**

```
global# zonecfg -z s8-zone info
```

**14 (Optional) Use the info subcommand to check the hostid:**

```
global# zonecfg -z s8-zone info attr
```

**Next Steps**

---

**Tip** – After you have configured the branded zone, it is a good idea to make a copy of the zone's configuration. You can use this backup to recreate the zone in the future. As superuser or Primary Administrator, print the configuration for the zone `s8-zone` to a file. This example uses a file named `s8-zone.config`.

```
global# zonecfg -z s8-zone export > s8-zone.config
```

---

**See Also** For additional components that can be configured using `zonecfg`, see *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*. The guide also provides information on using the `zonecfg` command in either command-line or command-file mode. For more information about adding ZFS file systems, see “Adding ZFS File Systems to a Non-Global Zone” in *Oracle Solaris ZFS Administration Guide*

# Installing the solaris8 Zone

---

This chapter covers installing a solaris8 branded zone.

## The zoneadm Command

The `zoneadm` command described in the [zoneadm\(1M\)](#) man page is the primary tool used to install and administer non-global zones. Operations using the `zoneadm` command must be run from the global zone. The following tasks can be performed using the `zoneadm` command:

- Verify a zone
- Install a zone
- Boot a zone
- Display information about a running zone
- Halt a zone
- Reboot a zone
- Uninstall a zone
- Relocate a zone from one point on a system to another point on the same system
- Provision a new zone based on the configuration of an existing zone on the same system
- Migrate a zone, used with the `zoncfg` command

## Migration Process

In addition to unpacking files from the Solaris 8 archive, the install process performs checks, required postprocessing, and other functions to ensure that the zone is optimized to run on the host. If you are migrating a zone to a new host, see [“Zone Migration and Initial Boot”](#) on [page 38](#).

# solaris8 Zone Installation Images

## Types of Images

- You can use an image of a Solaris 8 system that has been fully configured with all of the software that will be run in the zone. See [“Creating the Image for Directly Migrating Solaris 8 Systems Into Zones”](#) on page 24.
- You can use an image provided by Sun to create and install the solaris8 branded zone.

## Image sysidcfg Status

The sample Solaris 8 image provided by Sun has been processed using the `sys-unconfig` command described in [sys-unconfig\(1M\)](#). That is, it does not have a hostname or name service configured, which is also known as "as-manufactured." See [“How to Log In to the Zone Console to Complete System Identification”](#) on page 39.

If you created a Solaris 8 system archive from an existing system and use the `-p` (preserve `sysidcfg`) option when you install the zone, then the zone will have the same identity as the system used to create the image.

If you use the `-u` (`sys-unconfig`) option when you install the target zone, the zone produced will not have a hostname or name service configured.



---

**Caution** – You *must* use either the `-p` option or the `-u` option. If you do not specify one of these two options, an error results.

---

## ▼ How to Install the Zone

You must be the global administrator in the global zone to perform this procedure.

---

**Note** – This example procedure uses the blank archive image, `solaris8-image.flar`. This archive is in the `sys-unconfig` state. See [“Software Download”](#) on page 17 to obtain this file.

For information on creating images of Solaris 8 systems, see [“Creating the Image for Directly Migrating Solaris 8 Systems Into Zones”](#) on page 24.

---

- 1 **Become superuser, or assume the Primary Administrator role.**
- 2 **Install the configured zone `s8-zone` by using the `zoneadm` command with the `install -a` option and the path to the archive.**

```
global# zoneadm -z s8-zone install -u -a /net/server/s8_image.flar
```

You will see various messages as the installation completes. This can take some time.

---

**Note** – To retain the `sysidcfg` identity from a system image that you created without altering the image, use the `-p` option after the `install` subcommand. To remove the system identity from a system image that you created without altering the image, use the `-u` option. The `sys-unconfig` occurs to the target zone.

---

**3 (Optional) If an error message is displayed and the zone fails to install, type the following to get the zone state:**

```
global# zoneadm list -cv
```

| ID | NAME    | STATUS     | PATH                 | BRAND    | IP     |
|----|---------|------------|----------------------|----------|--------|
| 0  | global  | running    | /                    | native   | shared |
| -  | s8-zone | configured | /export/home/s8-zone | solaris8 | shared |

- If the state is listed as configured, make the corrections specified in the message and try the `zoneadm install` command again.
- If the state is listed as incomplete, first execute this command:

```
global# zoneadm -z my-zone uninstall
```

Then make the corrections specified in the message, and try the `zoneadm install` command again.

**4 When the installation completes, use the `list` subcommand with the `-i` and `-v` options to list the installed zones and verify the status.**

```
global# zoneadm list -iv
```

You will see a display that is similar to the following:

| ID | NAME    | STATUS    | PATH                 | BRAND    | IP     |
|----|---------|-----------|----------------------|----------|--------|
| 0  | global  | running   | /                    | native   | shared |
| -  | s8-zone | installed | /export/home/s8-zone | solaris8 | shared |

### Example 5-1 solaris8 Zone Installation

```
zoneadm -z s8-zone install -a /net/machinename/s8_image.flar
 Log File: /var/tmp/s8-zone.install.21207.log
 Source: /net/machinename/s8_image.flar
 Installing: This may take several minutes...
 Postprocessing: This may take a minute...

 Result: Installation completed successfully.
 Log File: /export/home/s8-zone/root/var/log/s8-zone.install.21207.log
```

**More Information**    **Installer Options**

| Option | Description                                                                                                                                                      |
|--------|------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| -a     | Location of archive from which to copy system image. Full flash archive and cpio, gzip compressed cpio, bzip compressed cpio, and level 0 ufsdump are supported. |
| -d     | Location of directory from which to copy system image.                                                                                                           |
| -p     | Preserve system identity.                                                                                                                                        |
| -s     | Install silently.                                                                                                                                                |
| -u     | sys-unconfig the zone.                                                                                                                                           |
| -v     | Verbose output.                                                                                                                                                  |

**Troubleshooting**    If an installation fails, review the log file. On success, the log file is in two places: /var/tmp in the global zone, and /var/log inside the zone. On failure, the log file is in /var/tmp.

If a zone installation is interrupted or fails, the zone is left in the incomplete state. Use `uninstall -F` to reset the zone to the configured state. See [“How to Uninstall a Zone” in \*System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones\*](#) for more information.

# Booting a Zone and Zone Migration

---

This chapter describes how to boot the installed zone, and also discusses how to migrate the zone to another machine.

If you are booting a zone that does not have the hostname or name service configured, read [Chapter 7, “About Zone Login and Post-Installation Configuration,”](#) first.

## About Booting the Zone

Booting a zone places the zone in the running state. A zone can be booted from the ready state or from the installed state. A zone in the installed state that is booted transparently transitions through the ready state to the running state. Zone login is allowed for zones in the running state.

### ▼ How to Boot the Zone

You must be the global administrator in the global zone to perform this procedure.

- 1 **Become superuser, or assume the Primary Administrator role.**
- 2 **Use the `zoneadm` command with the `-z` option, the name of the zone, which is `s8-zone`, and the `boot` subcommand to boot the zone.**

```
global# zoneadm -z s8-zone boot
```

- 3 **When the boot completes, use the `list` subcommand with the `-v` option to verify the status.**

```
global# zoneadm list -v
```

You will see a display that is similar to the following:

| ID | NAME   | STATUS  | PATH | BRAND  | IP     |
|----|--------|---------|------|--------|--------|
| 0  | global | running | /    | native | shared |

```
1 s8-zone running /export/home/s8-zone solaris8 shared
```

**See Also** For more information on booting zones and boot options, see [Chapter 20, “Installing, Booting, Halting, Uninstalling, and Cloning Non-Global Zones \(Tasks\)”](#), in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*.

## Migrating a solaris8 Zone to Another Host

### About Detaching and Attaching the Zone

A solaris8 zone can be migrated to another host by using the zoneadm command with the detach and attach subcommands. This process is described in “[About Migrating a Zone](#)” in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones* and “[How to Migrate A Non-Global Zone](#)” in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*.

To attach the solaris8 zone to the new host, you **must** use the -F option. This option is used to skip package and patch validation, which are not needed for branded zones.

**EXAMPLE 6-1** Sample attach Command

```
host2# zoneadm -z zonename attach -F
```

### Zone Migration and Initial Boot

During the process of installing the solaris8 branded zone, a physical-to-virtual conversion is automatically performed. When a solaris8 branded zone is migrated to a new host, this process must be repeated to ensure that the zone is optimized to run on the new host. The first time that the zone attempts to boot on the new host it will detect whether the s8\_p2v conversion command was run. The zone will not boot if the command has not been run again.

If you are booting a migrated s8-zone zone on a new host for the first time, run the following command before you boot the zone:

```
global# /usr/lib/brand/solaris8/s8_p2v zonename
```

# About Zone Login and Post-Installation Configuration

---

This chapter discusses logging in to zones, using `sysidcfg` to complete system identification, making modifications to `/etc/system`, and using `ssh` X11 forwarding in a `solaris8` zone.

## Internal Zone Configuration

Note that you perform the internal zone configuration when you log in to the `sys-unconfig` zone for the first time. This is described in “[Internal Zone Configuration](#)” in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*.

When responding to the system question asking whether the time is correct, do not modify the time displayed. If you modify the time, the system identification will fail and return to the time setting prompt, because non-global zones cannot modify the system clock by default. You must also accept the network configuration already specified in `zonecfg` for shared-IP zones.

If you plan to use an `/etc/sysidcfg` file to perform initial zone configuration, as described in “[How to Use an /etc/sysidcfg File to Perform the Initial Zone Configuration](#)” in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*, create the `sysidcfg` file and place it the zone's `/etc` directory before you boot the zone.

### ▼ How to Log In to the Zone Console to Complete System Identification

You must be the global administrator in the global zone to perform this procedure.

- 1 **Become superuser, or assume the Primary Administrator role.**

- 2 Use the `zlogin` command with the `-C` option and the name of the zone, `s8-zone` in this procedure.

```
global# zlogin -C s8-zone
```

- 3 From another terminal window, boot the zone.

```
global# zoneadm -z s8-zone boot
```

You will see a display similar to the following in the `zlogin` window:

```
[NOTICE: Zone booting up]
```

- 4 The first time you log in to the console, you are prompted to answer a series of questions. Your screen will look similar to this:

```
SunOS Release 5.8 Version Generic_Virtual 64-bit
Copyright 1983-2000 Sun Microsystems, Inc. All rights reserved
Use is subject to license terms.
```

```
Hostname: s8-zone
Select a Language
```

- 0. English
- 1. fr

Please make a choice (0 - 1), or press h or ? for help:

```
Select a Locale
```

- 0. English (C - 7-bit ASCII)
- 1. Canada-English (ISO8859-1)
- 2. Thai
- 3. U.S.A. (en\_US.ISO8859-1)
- 4. U.S.A. (en\_US.ISO8859-15)
- 5. Go Back to Previous Screen

Please make a choice (0 - 5), or press h or ? for help:

```
What type of terminal are you using?
```

- 1) ANSI Standard CRT
- 2) DEC VT52
- 3) DEC VT100
- 4) Heathkit 19
- 5) Lear Siegler ADM31
- 6) PC Console
- 7) Sun Command Tool
- 8) Sun Workstation
- 9) Televideo 910
- 10) Televideo 925
- 11) Wyse Model 50
- 12) X Terminal Emulator (xterms)
- 13) Other

```
Type the number of your choice and press Return:
```

```
12
.
.
.
```

For the approximate list of questions you must answer, see “[Internal Zone Configuration](#)” in *System Administration Guide: Oracle Solaris Containers-Resource Management and Oracle Solaris Zones*.

- 5 (Optional) If you are not using two windows as described in step 3, you might have missed the initial prompt for configuration information. If you see the following system message at zone login instead of a prompt:

```
[connected to zone zonename console]
```

Press Return to display the prompt again.

If you enter an incorrect response and try to restart the configuration, you might experience difficulty when you attempt the process again. This occurs because the `sysidtools` can store your previous responses.

If this happens, use the following workaround from the global zone to restart the configuration process.

```
global# zlogin -S zonename /usr/sbin/sys-unconfig
```

For more information on the `sys-unconfig` command, see the [sys-unconfig\(1M\)](#) man page.

## Applying Solaris 8 Patches in the Container

Solaris 8 patches can be applied to the Solaris 8 environment from within the container, using the same process as on a standalone system. Obtain the patch and, while running in the `solaris8` zone, run `patchadd` to install the patch. Note that because the kernel is actually a Solaris 10 kernel, patches that alter any Solaris 8 kernel bits will not take effect. In this case, the equivalent Solaris 10 patch should be applied in the global zone if needed. Even though Solaris 8 patches delivering kernel updates have no effect within the zone, they are still required to satisfy patch dependencies.

For more information on patching Solaris 8 systems, see Chapter 22 Patch Administration (Overview) in *System Administration Guide, Volume 1*.

## Tuning /etc/system and Using Resource Controls

In Solaris 8, System V and file descriptor limits are tuned by modifying `/etc/system` and rebooting the machine to have the modifications take effect. In Solaris 10, these limits can be tuned dynamically through resource controls.

For a `solaris8` branded zone, the contents of `/etc/system` are used to set project and process resource controls when the zone boots. If `/etc/system` is not tuned, the default file descriptor and System V limits from Solaris 8 are used.

The effective limits within the zone will be the lower of the zone's `/etc/system` or the zone's `zonecfg` settings. To view the effective limits, run the `sysdef` command described in the [sysdef\(1M\)](#) in the zone.

You must be the zone administrator to modify `/etc/system` within the `solaris8` branded zone, and reboot it to have the changes take effect. Because `/etc/system` can be modified within the zone, the global administrator can use the `zonecfg` command from the global zone to set limits for the zone.

Use the `prctl` command from the global zone to view the default resource control settings. The example shows that the default settings on the `init` process restrict the System V limits.

#### EXAMPLE 7-1 View Default Settings on the `init` Process in a `solaris8` Zone

```
global# prctl 'pgrep -x init -z s8zone'
...
process.max-msg-messages
 privileged 40 - deny
 system 4.29G max deny
process.max-msg-qbytes
 privileged 4.00KB - deny
 system 16.0EB max deny
process.max-sem-ops
 privileged 10 - deny
 system 2.15G max deny
process.max-sem-nsems
 privileged 25 - deny
 system 32.8K max deny
process.max-file-descriptor
 basic 256 - deny
 privileged 1.02K - deny
 system 2.15G max deny
...
project.max-shm-memory
 privileged 100MB - deny
 system 16.0EB max deny
project.max-shm-ids
 privileged 100 - deny
 system 16.8M max deny
project.max-msg-ids
 privileged 50 - deny
 system 16.8M max deny
project.max-sem-ids
 privileged 10 - deny
 system 16.8M max deny
...
```

## Modifying `/etc/system`

For applications that require these tunings to be increased, the zone administrator can modify `/etc/system` within the `solaris8` branded zone, and reboot it. This procedure is identical to that used to increase tunings on a native Solaris 8 system.

## Using zonecfg to Set Resource Controls

The `zonecfg` command can be used from the global zone to restrict the System V limits within the zone.

**EXAMPLE 7-2** Setting Resource Controls From the Global Zone

You must be the global administrator in the global zone to perform these procedures.

```
global# zonecfg -z mys8zone set max-shm-memory=100m
```

If you use `zonecfg` after initial zone creation, reboot the zone to have the change take effect.

```
global# zoneadm -z mys8zone reboot
```

## Running X11 Applications in a solaris8 Branded Zone

ssh X11 forwarding is the preferred method for running Solaris 8 X11 applications, including 3-D and graphics intensive applications, within a `solaris8` zone. 3-D applications can only be run on a system that supports 3-D graphics in the global zone.

### ▼ How to Use ssh X11 Forwarding

To use X11 forwarding, you must meet the following requirements:

- Networking must be enabled for the `solaris8` zone
- Because Solaris 8 does not include the `ssh` login by default, `ssh` must be downloaded and installed in the zone.

- 1 **Become superuser, or assume the Primary Administrator role.**
- 2 **Enable networking in the zone as described in “How to Configure a solaris8 Branded Zone” on page 29.**
- 3 **Download `ssh` from [www.openssh.org](http://www.openssh.org) (<http://www.openssh.org>), [www.sunfreeware.com](http://www.sunfreeware.com) (<http://www.sunfreeware.com>) or [www.blastwave.com](http://www.blastwave.com) (<http://www.blastwave.com>) and install it in the zone.**
- 4 **When `ssh` is running in the zone, log directly into the X server running on the console of the global zone.**
- 5 **To enable `ssh` X11 forwarding and run X applications remotely, use the following command:**  

```
ssh -X zone_host_name
```

**Troubleshooting** Any application that delivers its own Xserver extensions will not work with `ssh -X` forwarding and is not currently supported within `solaris8` branded zones.

# Troubleshooting Miscellaneous Solaris 8 Branded Zones Problems

---

This chapter contains zones troubleshooting information.

## Library Version Affecting Application Behavior

Solaris 8 branded zones use what is known as the *alternate* `libthread` library. This is the version of `libthread` that is delivered in `/usr/lib/lwp` on Solaris 8. This library has become the standard thread library on Solaris 10, but that was not the case for Solaris 8.

In general, the alternate `libthread` solves various threading issues that existed with the default library and the alternate is required by the underlying thread model provided by the Solaris 10 kernel. However, there are some subtle behavioral differences with this library, as compared to the default library, on earlier releases of Solaris 8.

If these differences cause an application to behave differently within a `solaris8` branded zone, as compared to its behavior on native hardware, ensure that the zone has up-to-date patches for `libthread`. Install the latest version of patch 108827. Depending on the version of Solaris 8 installed in the zone, this might require additional patches be installed to fulfill all of the patch dependencies. Later releases, such as Solaris 8 2/04, already have a version of the alternate `libthread` that works well within a `solaris8` branded zone.



# solaris8(5) Man Page

---

## NAME

solaris8—Solaris 8 container

## Description

The `solaris8` container uses the branded zones framework described in [brands\(5\)](#) to enable Solaris 8 binary applications to run unmodified on a machine with the latest Oracle Solaris 10 Operating System kernel.

The `solaris8` brand includes the tools necessary to install a Solaris 8 system image into a non-global zone. The brand supports the execution of 32-bit and 64-bit Solaris 8 applications on SPARC machines running the latest Solaris operating system.

## Configuration and Administration

The `solaris8` brand supports the whole root non-global zone model. All of the required Solaris 8 software and any additional packages are installed into the private file systems of the zone.

The `zonecfg(1M)` utility is used to configure a `solaris8` branded zone. Once a branded zone has been installed, that zone's brand cannot be changed or removed. The `zoneadm(1M)` utility is used to report the zone's brand type and administer the zone. The `zlogin(1)` utility is used to log in to the zone.

The `solaris8` brand installer supports installing the zone from an image of an installed Solaris 8 system. This can be a full `flash_archive(4)`, `cpio(1)` archive optionally compressed with `gzip(1)` or `bzip2(1)`, or `pax(1)` xustar archive. The image can also be a level 0 `ufsdump(1M)`, or a path to the top-level of a Solaris 8 system's root directory tree. The zone cannot be installed from standard Solaris 8 distribution media. The `zoneadm(1M)` brand-specific subcommands accept the following arguments:

|                                                                          |                                                                                                                                                                                                                                                                        |
|--------------------------------------------------------------------------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| <code>install [-a <i>archive</i>] [-d <i>path</i>] [-s] [-u] [-v]</code> | Install the specified Solaris 8 system image into the zone. Either the <code>-u</code> or <code>-p</code> option is required and either the <code>-a</code> or <code>-d</code> option is required.                                                                     |
| <code>-a <i>archive</i></code>                                           | The path to a <code>flash_archive(4)</code> , <code>ufsdump(1M)</code> , or <code>pax(1)</code> xustar archive of an installed Solaris 8 system. The <code>cpio</code> archives may be compressed using the <code>gzip(1)</code> or the <code>bzip(1)</code> commands. |
| <code>-d <i>path</i></code>                                              | The path to the root directory of an installed Solaris 8 system.                                                                                                                                                                                                       |
| <code>-p</code>                                                          | Preserve the system configuration after installing the zone.                                                                                                                                                                                                           |
| <code>-s</code>                                                          | Install silently.                                                                                                                                                                                                                                                      |
| <code>-u</code>                                                          | Run <code>sys-unconfig(1M)</code> on the zone after installing it.                                                                                                                                                                                                     |
| <code>-v</code>                                                          | Verbose output from the install process.                                                                                                                                                                                                                               |

## Application Support

The `solaris8` zone only supports user-level Solaris 8 applications. You cannot use Solaris 8 device drivers, Solaris 8 kernel modules, or Solaris 10 only file systems, such as `zfs(1M)` delegated datasets,, from inside a `solaris8` zone. However, you can add `fs` resources in `zonecfg` with `type=zfs`.

Native Solaris debugging tools such as DTrace (see `dttrace(1M)`) can be applied to Solaris 8 processes executing inside the zone, but the tools themselves must be running in the global zone.

## Zone Migration

During the process of installing the zone, a "physical to virtual" conversion is automatically performed. After a `solaris8` branded zone is migrated to a new host, this process should be repeated to ensure that the zone is optimized to run on the new host. The first time that the zone attempts to boot on the new host it will detect this situation and the zone will not boot until the following command is run:

```
/usr/lib/brand/solaris8/s8_p2v zonename
```

---

## Attributes

See [attributes\(5\)](#) for a description of the following attributes:

| ATTRIBUTE TYPE      | ATTRIBUTE VALUE            |
|---------------------|----------------------------|
| Availability        | SUNWs8brandr, SUNWs8brandu |
| Interface Stability | Evolving                   |

## See Also

[pax\(1\)](#), [zlogin\(1\)](#), [zonename\(1\)](#), [dtrace\(1M\)](#), [flarcreate\(1M\)](#), [ufsdump\(1M\)](#), [zfs\(1M\)](#), [zoneadm\(1M\)](#), [zonecfg\(1M\)](#), [flash\\_archive\(4\)](#), [brands\(5\)](#), [zones\(5\)](#)



# Index

---

## A

attaching solaris8 branded zone, 38

## B

booting a solaris8 zone, 37

brand, 11

branded zone, 11

- device support, 12

- file system support, 12

- Oracle Solaris 8, 14

- privileges, 12

- running processes, 12

BrandZ, 11

## D

download, 17

DTrace, 14

## F

flarcreate, 24

## H

Host ID, 25

hostid emulation, 25

## I

installations, solaris8, 34

## M

media, 17

migrating and booting a solaris8 zone, 38

## N

native, zone, 11

non-native, zone, 11

## O

Oracle Solaris 10 features, 14

## P

path on ZFS, 15

privileges in solaris8 branded zone, 28

## S

Solaris 10 system requirements, 17

Solaris 8 image creation, 24

Solaris 8 system evaluation, 23

solaris8, 14

- solaris8 branded zone
  - attaching, 38
  - boot procedure, 37
  - configuration overview, 28
  - configuring, 29
  - file systems, 28
  - migration, 38
  - privileges, 28
- solaris8 installations, 34
- solaris8 sysidcfg, 39
- sysidcfg, solaris8, 39

## **Z**

- ZFS and solaris8, 15
- ZFS zonepath, 15
- zone
  - branded, 11
  - native, 11
  - non-native, 11
- zoneadm command overview, 33
- zonecfg, solaris8 branded zone process, 28