

**Oracle® Utilities Work and Asset
Management**

Configuration Guide

Release 1.9.0.3

E22039-01

July 2011

Oracle® Utilities Work and Asset Management Configuration Guide Release 1.9.0.3

Doc v1 rev.0

Copyright ©Copyright ©1986, 2011, Oracle and/or its affiliates. All rights reserved.
Oracle and/or its affiliates. All rights reserved.

Primary Author: TUGBU Documentation

Contributing Author: n/a

Contributor: n/a

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this software or related documentation is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT RIGHTS

Programs, software, databases, and related documentation and technical data delivered to U.S. Government customers are “commercial computer software” or “commercial technical data” pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, duplication, disclosure, modification, and adaptation shall be subject to the restrictions and license terms set forth in the applicable Government contract, and, to the extent applicable by the terms of the Government contract, the additional rights set forth in FAR 52.227-19, Commercial Computer Software License (December 2007). Oracle America, Inc., 500Oracle Parkway, Redwood City, CA 94065.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications which may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third party content, products and services. Oracle Corporation and its affiliates will not be responsible for any lost, costs, or damages incurred due to your access to or use of third party content, products or services.

Contents

Overview	35
Configuration Guide	35
1 General System Setup	36
Audit Log	36
Batch Processes	36
Refresh Materialized View(s)	36
Business Rules	37
Asset Navigator Rule	37
Copy/Paste Object IDs Rule	37
Default Directories Rule	38
Default File Locations Rule	39
Do Approvals Query	40
Do Attachments Query	40
Do Notes Query	40
Drill-down Configuration Rule	41
Home Page Component Alias	41
MDI Window Title Rule	42
E-Mail Configuration Rule	43
Optional Message Presentation Rule	44
PIN Processing Administration Rule	45
Primary Menu Rule	46
Restrict List of Values Rule	47
Spell Check Rule	48
UDFs - Auto Copy Across Modules Rule	49
Unit of Measurement Rule	50
Code Tables	50
Code Table 54: Note Types	50
Code Table 186: Manufacturers	50
Event Queue	51
Clearing Events	51
Processing Retries	51
Functions	51
DISABLE CUSTOM SQL	51
Entity Relationship Viewer	52
ESRI3 Viewer	52
GIS Viewer	52
Graph Viewer	52
Issue Uncompiled Objects Msg	52
News Administration	52
Reorder Wizard	52
Installation Parameters	52
AUDIT LOG- Objects beginning with SAUT	52
ENABLE PASSWORD RESET	52
PHONE_NUMBER_FORMAT	52
SPELL CHECK	52
Transaction Logs - Objects beginning with SDBT	53
WORKFLOW MESSAGE DIALOG	53
Database, Install and System Administration	53

E-Mail Integration	53
Enhanced Security	53
Failed Logon Attempts	54
Managing Log Files	54
Proxies	55
Application Server Configuration	55
Security Certificate	56
Single Sign On	56
Authentication Redirection	57
Transaction Logs.....	58
Charts, Metrics, and Reports.....	58
Localization.....	58
Field Localization View in Modules Administration Forms	59
Locale Fields in the Plant Module	59
Using Currency Codes for Localization	60
Using Code Tables for Localization	61
Configuring Internationalized Numbers	61
Batch Processing	62
Batch Processes	62
Job Manager - sdbp_job_error_log ((job_in, plant_in, sysdate-365);	62
Purge Data - sdbp_purge_data;	62
Run All Batch - sdbp_run_all_batch;	62
Business Rules	63
Batch Job Control Rule	63
Batch Purge Criteria Rule	64
Batch Purge Parameters Rule	65
Batch Process Descriptions.....	66
Reports	71
S_RPT097 - Job Manager Log Report	71
Installation Parameters	72
BATCH JOB DEBUG MODE	72
Approval Limit Module.....	73
Fields	73
Approval Title and Description	73
Type	73
Employee Number and Username	73
Alert?	73
Active?	73
Document and Limit	74
Copy Record	74
APPROVAL - COPY RECORD	74
Modules and Activities Requiring an Approval Title	74
Routing List Module.....	75
Fields	75
Title	75
Description	75
Sequence	75
Mandatory	75
Notify Only	75
Business Rules	75
Approval Routing Rule	75
Batch Processes	76
Clear Event Queue - sdbp_event_queue;	76
Copy Record	76
ROUTELIST - COPY RECORD	76
Process flow:	77
2 Administration Subsystem	78

Business Rules Module	79
Reports	80
S_RPT002 - Business Rule Report	80
Custom Rules	80
Integration Rules	82
Interface Rules	83
Interfaces Rule	83
Interface Parameters Rule	84
Obsolete Rules	84
Advanced Materials Management Option (AMMO)	84
AMMO Sequence Numbering Tables	84
Buyers Module	86
Fields	86
Stores Reorder	86
Update Approved PO	86
Update Issued PO	86
Code Table and Codes Module	87
Fields	87
Table Number	87
Description	87
Type	87
Code Length	87
Code	87
Description	87
Link	88
Reports	88
S_RPT015 - Code Table Definition Report	88
S_RPT001 - Code Table Report	88
System Code Tables	88
DBA Code Tables	90
Obsolete Code Tables	91
Advanced Materials Management Option (AMMO)	91
Configuration Guide Module	93
Code Tables	93
Code Table 560 - 565: Configuration Codes	93
Currency Exchange Rates	93
Fields	93
Currency	93
Effective Date, Exchange Rate, and Comments	93
Fine Grain Access Module	94
Fields	94
Sequence No.: FGA ID	94
Status	94
Description	94
Owner	95
Table Name	95
Condition	95
FGA Responsibility Module	95
Views	95
Assigned Users	96
Help Form Module	97
Customizing the Help Form	97
Installation Parameters Module	98
Parameter Descriptions	98
BATCH JOB DEBUG MODE	98
CHART THUMBNAIL GENERATION	98
CHART THUMBNAIL PROCESSING	98
CHART_INVENTORY_VALUATION	98
ENABLE PASSWORD RESET	98
INDEX_INITIAL_EXTENT	99

INDEX_NEXT_EXTENT	99
INDEX_TABLE_SPACE	99
JUMBO_SIZE_INITIAL_EXTENT	99
JUMBO_SIZE_NEXT_EXTENT	99
LARGE_SIZE_INITIAL_EXTENT	99
LARGE_SIZE_NEXT_EXTENT	99
LICENSE OWNER	99
MID_SIZE_INITIAL_EXTENT	99
MID_SIZE_NEXT_EXTENT	99
PHONE_NUMBER_FORMAT	99
PK_INITIAL_EXTENT	99
PK_NEXT_EXTENT	99
PK_TABLESPACE	99
PRIMAVERA	99
SCHEDULING TOTAL EST HRS DISP	99
SIA_TABLEOWNER	99
SMALL_SIZE_INITIAL_EXTENT	100
SMALL_SIZE_NEXT_EXTENT	100
SPELL CHECK	100
SUPER USER ROLE	100
TABLEOWNER	100
TABLESPACE_NAME	100
TEMPORARY_TABLESPACE_NAME	100
TINY_SIZE_INITIAL_EXTENT	100
TINY_SIZE_NEXT_EXTENT	100
Objects beginning with SDBT	100
Objects beginning with SAUT	100
Objects beginning with SABI	100
Modules Administration - Forms Module.....	101
Required Fields, Enter Data, Secondary Required Fields, and Status Required fields	101
Field Localization View	101
Module Reports	101
Copy Record View	102
Special LOVs View	103
Custom Menus View	103
Selection Order By View	103
Duplicate View	104
Allow Duplicate View	104
Modules Administration - SIA	104
Fields	104
Field Source and Field Name	104
Default Value	104
System	105
Required	105
Secondary Fields View	105
Charts and Metrics	106
Responsibilities	106
Filtered Metrics	106
Charts	106
Maximum Chart Records	106
Charts Home Directory	106
Notes on Charts in Office 2007	107
Batch Processes	108
Generate All Chart Images	108
Generate Charts	108
Generate Metrics	108
Business Rules	109
Charts and Metrics Settings Rule	109
Installation Parameters	109
CHART_INVENTORY_VALUATION	109
CHART THUMBNAIL GENERATION	110
CHART THUMBNAIL PROCESSING	110
Functions	110

Display Trusted Sites Link	110
Report Administration Module	111
Business Rules	111
Web Configuration Rule	111
Responsibility Module	113
Responsibility Types	113
Copy Record	114
RESPONBL - COPY RECORD	114
Application Security	114
Sequence Numbers Module	116
Fields	116
Table Name	116
Sequence Number	116
Prefix	116
Length	116
System	116
User Profile Module	117
Administrator Access to User Profile Records	117
Configuration Scenarios	117
Business Rules	119
Password Security Rule	119
Printer Alias Rule	120
Batch Processes	121
Synchronize User - sdbp_clean_user_n_user_profile;	121
Copy Record	121
USERPROF - COPY RECORD	121
Functions	121
User Profile Administrator	121
Activate Pins	121
User-Defined Fields Module	122
User-Defined Fields on Related Tables	122
UDF Setup Window	122
Table Definition	123
Determining Which Windows Show UDFs	123
Workflow Groups Module	125
Fields	125
Group Owner	125
User Name	125
Public	125
Group Name	125
Description	125
People in Group and People Not in Group	125
The Add Button	125
The Add All Button	125
The Remove Button	125
The Remove All Button	125
Copy Group	125
3 Resource Subsystem	126
Account Structure Module	126
Fields	126
Segment Name	126
Length	126
Use Code Table?	126
Required?	126
Delimiter Character and Position Indicator	126
Code Tables	127
Code Table 251 to Code Table 260: ACCOUNT SEGMENT 1 to 10	127

Accounting Periods Module	128
Business Rules	128
Account Period Override Rule	128
Pay Periods Module	129
Business Rules	129
End of Period Processing Rule	129
Department Module	132
Fields	132
Department and Description	132
Parent and Child Department Fields	132
Charts	132
S_CHT126 - Departmental Costs Summary	132
Copy Record	132
DEPT- COPY RECORD	132
Area Module	132
Fields	132
Department and Description	132
Area and Description	132
Copy Record	132
AREA - COPY RECORD	132
Account Module	133
Fields	133
Account Number	133
Reference ID Field	133
Work Request Route Field	133
Budget Type Field	133
Business Rules	134
Budget Checking Rule	134
Budget Checking by Document Rule	135
Budget Checking Skip Accounts Rule	136
Expense Codes Rule	136
Code Tables	137
Code Table 251 to Code Table 260: ACCOUNT SEGMENT 1 to 10	137
Code Table 1195 - CCB Expense	137
Code Table 1196 - CCB Install Remove Flag	137
Copy Record	137
ACCTDATA - COPY RECORD	137
Functions	137
View External Actual Costs	137
Reports	137
S_RPT204 - Purchase Order Expensing Account Detail Report	137
Views	138
Period Costs	138
Account Distribution Module	139
Fields	139
Sequence No.: Account Distribution ID	139
Batch Processes	139
ACCOUNT DISTRIBUTION TEMPLATE - sdbp_default_accounts_status	139
Copy Record	139
ACCTTMPL - COPY RECORD	139
Regulatory Account Module	140
Fields	140
WIP Account #	140
Usage Code Field	140
Overhead Class	140
Business Rules	140
Regulatory Account Usage Codes	140
Regulatory Account Options	141
Regulatory Account Overhead Class	141
Batch Processes	142
Regulatory Account Cost - sdbp_regulatory_account_cost;	142

Year End Overhead Distribution - sdbp_year_end_oh_cost_dist;	142
Process Fixed Assets - sdbp_work_order.fixed_asset;	142
Copy Record	142
REGACCT - COPY RECORD	142
Storeroom Module.....	143
Business Rules	143
Available Quantity Calculation Rule	143
Invoice Setup Criteria Rule	144
Storeroom Demand Allocation Rule	146
Code Tables	146
Code Table 69: Reorder Reviewer Code	146
Code Table 187: Inventory Adjustment Reason Codes (Inventory Quantity Adjustments Action)	146
Copy Record	147
STORERM -COPY RECORD	147
Functions	147
Reorder Wizard	147
Storeroom ABC	147
Storeroom Adjustment	147
Storeroom Reorder	147
Batch Processes	147
Cost Invoice - sdbp_cost_invoice.cost_invoice;	147
Cost Stock - sdbp_cost_stock.cost_stock;	147
End of Period Processing - sdbp_end_of_period_processing;	147
Reset Demand Quantity - sdbp_storeroom_demand;	147
RESET ON ORDER QUANTITY - sdbp_storeroom_on_order;	148
Stock Reorder - sdbp_stock_reoder.stock_reorder;	148
Storeroom Demand - sdbp_storeroom_demand;	148
Storeroom Repair Costs - sdbp_storeroom_repair_costs;	148
Charts	148
S_CHT127 - Inventory Turns	148
S_CHT128 - Inventory Valuation	148
Reports	148
S_RPT050 - Catalog Non-Usage Report	148
S_RPT016 - Catalog (without Quantities) Report	148
S_RPT026 - Inventory Picklist Report	148
S_RPT034 - New Stock Items Report	149
S_RPT032 - New Storeroom Items Report	149
S_RPT035 - Overstock Report	149
S_RPT202 - Purchase Order Inventory Item Cost Report	149
S_RPT115 - Stock Transfer Report	149
S_RPT033 - Storeroom Activity Report	149
S_RPT017 - Storeroom Report with Quantities	149
S_RPT019 - Storeroom Value by Class	149
S_RPT106 - Storeroom Value By Stock Code	149
S_RPT083 - Tax Report for Inventoried Stocked Items	149
S_RPT082 - Tax Report for Non-Stocked Items	149
S_RPT036 - Understock Report	149
Storeroom Setup Module.....	150
Business Rules	150
ABC Inventory Rule	150
Code Tables	150
Code Table 4: Storeroom Types (Length = 10)	150
Copy Record	151
STORESET - COPY RECORD	151
Master Catalog Module	152
Fields	152
Sequence No.: Stock Code	152
Business Rules	152
Procurement Level Rule (Associated Stock Codes View)	152
Shelf Life Rule (Associated Stock Codes View)	153
Update Primary Vendor Rule (Associated Stock Codes View)	153
Code Tables	154
Code Table 212: Item Class Codes (Length = 10)	154

Code Table 23: Unit of Measure (Length = 4)	154
Code Table 18: Purchasing Commodity Codes (Length = 20)	154
Code Table 159: Federal Tax Codes (Length = 1)	154
Code Table 160: State Tax Codes (Length = 1)	154
Code Table 161: Duty Codes (Length = 1)	154
Code Table 122: Commodity Category Codes (Length = 5)	154
Code Table 123: Commodity Composition (Length = 10)	154
Code Table 6: Hazardous Types (Length = 10)	154
Code Table 360: Quality Classes	154
Code Table 202: Storage Code (Length = 5)	155
Code Table 203: Special Requirements (Length = 5)	155
Code Table 209: Relationship Types (Associated Stock Codes View) (Length = 20)	155
Copy Record	155
CATALOG - COPY RECORD	155
Batch Processes	155
Create BOM Details - sdbp_create_bom_details.create_bom_details;	155
Charts	155
S_CHT127 - Inventory Turns	155
S_CHT128 - Inventory Valuation	155
Views	156
Crafts	156
Asset Module	157
Fields	157
Sequence No.: Asset ID	157
Asset Class	157
Approval Route Field (Permit Template Requirements View)	157
Maintenance Manager	157
Business Rules	158
Asset Runtime Rule	158
Criticality Override Rule	158
Planner Rule	159
Asset Depreciation Rule (Depreciation View)	160
Asset Key Segments Rule (Key Segments View)	161
Code Tables	161
Code Table 25: Building Codes	161
Code Table 29: Asset Types	162
Code Table 40: Criticality Codes	162
Code Table 61: Sources Type for Isolation (Sources to Isolate View)	162
Code Table 62: Required Position for Isolation (Sources to Isolate View)	162
Code Table 75 - 77: Asset Mobile fields 1-3	162
Code Table 105: Specification Categories for Assets	162
Code Table 107: Units (Depreciation View)	162
Code Table 110: Backlog Group	162
Code Table 130: Asset Interface Types - For Input / Output (Asset Interfaces View)	162
Code Table 230: Asset Record Types	162
Code Table 231: Location	163
Code Table 344: FMEA System Code	163
Code Table 1192: Riva Asset Type	163
Copy Record	163
ASSET	163
Functions	163
Create Activity Log From Asset	163
Create Emergency Work Order Asset	163
Create Work Order Asset	163
Create Work Request Asset	163
Create Specification	163
View GIS	163
Reports	164
S_RPT089 - Asset Listing By Type and Class Report	164
S_RPT091 - Historic Cost Performance by Asset Report	164
S_RPT090 - PM By Asset Report	164
S_RPT007 - Process Report with Asset Detail	164
Batch Processes	164
Cost Asset - sdbp_cost_asset;	164
Create BOM Details - sdbp_create_bom_details.create_bom_details;	164

Depreciate Assets - sdbp_end_period_depreciation;	164
Charts	164
S_CHT148 - Planned Vs. Unplanned Downtime	164
Metrics	164
S_MTRC6 - Percent of Planned Downtime - sdbp_metric_pct_plan_outage	164
Views	165
Associated Permit Requirements	165
Asset Depreciation Accounts	165
Asset Interfaces	165
Permit Template Requirements	166
Asset Cost Rollup	166
SV_ASSET_COST	166
SA_RULE_KEY	167
SA_ASSET_COST	167
SA_ASSET_COST	168
SA_EXTERNAL_ACTUAL_COST	168
Asset Activity Log Module.....	169
Fields	169
Sequence No.: Asset Log ID	169
Functions	169
Create Activity Log From Asset	169
Create Emergency Work Order Asset	169
Create Work Order Asset	169
Create Work Request Asset	169
Create Specification	169
Charts	169
S_CHT148 - Planned Vs. Unplanned Downtime	169
Metrics	170
S_MTRC6 - Percent of Planned Downtime - sdbp_metric_pct_plan_outage	170
Asset Class Module.....	171
Business Rules	171
Asset Depreciation Rule (Depreciation Parameters View)	171
Code Tables	172
Code Table 107: Units (Depreciation Parameters View)	172
Code Table 601: Asset Class Type	172
Copy Record	172
ASSETCLS - COPY RECORD	172
Views	172
Condition Assessment	172
Basis (Condition Assessment View)	172
Depreciation Parameters	174
Inspection Criteria	174
Condition Rating Basis	174
Category/Defect Type	174
Weight	175
Pass Fail Criteria and Points	175
Defect Classification and Grade	175
Defect Severity and Points	175
Asset Inspection Data Module	176
Fields	176
Sequence No.: Inspection ID	176
Code Tables	176
Code Table 23: Unit of Measure	176
Code Table 181: Asset Inspection Type	176
Code Table 182: Asset Inspection Reason	176
Code Table 183: Weather Condition	176
Code Table 244: Ground Condition	176
Code Table 245: Asset Inspection Severity (Observations View)	176
Reports	176
S_RPT150 - Asset Inspection Worksheet	176
Operational Data Module	178
Operational Tolerance Module	178

Fields	178
Sequence No.: Operational Tolerance ID	178
Code Tables	178
Code Table 70: Measurement Type	178
Copy Record	178
OPERTOL - COPY RECORD	178
Asset Data Module	179
Business Rules	179
Default Directories Rule	179
Component ID Module	180
Fields	180
Sequence No.: Component ID	180
Stock Code	180
Serial No.	180
Current Location	180
Bill of Materials	180
Last Install Date	180
Code Tables	181
Code Table 221: Component Types	181
Code Table 63: Tag Types	181
Code Table 230: Asset Record Types	181
Business Rules	181
Component ID Rule	181
Component Processing Rule	182
Default Directories Rule	183
Specification Upload Defaults	184
Web Configuration Rule	184
Copy Record	185
COMPID - COPY RECORD	185
Functions	185
Create Work Order Component	185
Create Work Request Component	185
Reports	185
S_RPT011 - Component ID Report	185
Component Upload	185
Compatible Structure Module	186
Fields	186
Sequence No.: Compatible Structure	186
Code Tables	186
Code Table 23: Unit of Measure	186
Code Table 225: Compatible Unit Business Unit	186
Code Table 226: Compatible Unit Class	186
Code Table 227: Compatible Unit Equipment Group	186
Copy Record	186
COMPSTRU	186
Functions	187
Update Active CU/CS	187
Compatible Unit Module	188
Fields	188
Sequence No.: Compatible Unit ID	188
Code Tables	188
Code Table 22: Vendor Characteristic Types (Characteristics View in Vendor module)	188
Code Table 23: Unit of Measure	189
Code Table 224: Compatible Unit Difficulty (Functions View)	189
Code Table 225: Compatible Unit Business Unit	189
Code Table 226: Compatible Unit Class	189
Code Table 227: Compatible Unit Equipment Group	189
Code Table 1197: Compatible Unit Type	189
Business Rules	190
Compatible Unit Defaults Rule	190
Compatible Unit Function Rule	191
Functions	191

Copy to New Compatible Unit	191
Show CU Location	191
Show CU on Work Order	191
Replace CU Material Item	191
Update Active CU/CS	192
Reports	192
S_RPT151 - Compatible Units Audit Report	192
Views	192
Accounting	192
Functions	192
Header (Master Catalog module)	192
Conductor Information view (Master Catalog module)	193
Bill of Materials Module	194
Fields	194
Sequence No.: BOM ID	194
Breakdown Indicator	194
Code Tables	194
Code Table 29: Asset Types	194
Copy Record	194
BOMDATA - COPY RECORD	194
Functions	195
Update BOM	195
Batch Processes	195
Create BOM Details - sdbp_create_bom_details.create_bom_details;	195
Reports	195
S_RPT081 - Bill of Material Report	195
Change Request Module.....	196
Fields	196
Sequence No.: Change Request No.	196
Next Approver Field	196
Code Tables	196
Code Table 136: Create New Asset Transaction Types	196
Code Table 141: Change Asset Information Transaction Types	196
Code Table 162: Dispose of Asset Transaction Types	196
Code Table 163: Change Asset Configuration Transaction Types	196
Code Table 165: Change Request Types	196
Code Table 166: Change Request Classes	196
Code Table 167: Impact Types	196
Code Table 168: Justification Types	196
Business Rules	197
Change Request Record Types Rule	197
Work Order Processing Rule	198
Copy Record	198
CHNGREQ - COPY RECORD	198
Functions	198
Change Request Actions for AVL	199
Change Request Asset	199
Change Request Catalog/Storeroom	199
Reports	199
S_RPT114 - Change Request Report	199
Employee Module	200
Fields	200
Sequence No.: Employee No.	200
Department and Area	200
Auto-Timesheet Schedule Fields	200
Business Rules	201
Craft Rates Rule	201
Scheduled Holidays	201
Timekeeping Authority Rule	202
Batch Processes	203
Auto Create Timesheets - sdbp_auto_create_timesheet.main;	203
Code Tables	203
Code Table 45: Training Courses (Training View)	203

Code Table 46: Payroll Group	203
Code Table 48: Leave Reason Codes (Scheduled Leave View)	203
Code Table 98: Administrative Department	203
Code Table 99: Classification	203
Code Table 111: Overtime Crew (Overtime Standings View)	203
Code Table 112: Overtime Zone (Overtime Standings View)	204
Code Table 208: Employee Job Title	204
Code Table 310: Supervisor Title	204
Copy Record	204
EMPLOYEE - COPY RECORD	204
Functions	204
Employee SSN	204
Employee Wage Rate	204
Reports	204
S_RPT012 - Employee Report	204
S_RPT078 - Holiday Overtime Standing Report	204
S_RPT061 - Wage Rate History Report	204
Attachments Modules	205
Business Rules	205
Attachment Print Configuration Rule	205
Attachment Drive Mapping Rule	206
Attachment Types Rule	206
Document Storage Types	207
Printer Alias Rule	207
Web Configuration Rule	208
Printing PDF Attachments	209
Checklist	209
Installation	209
Obtain Ghostscript	209
Install Ghostscript	209
Business Rule Settings for Ghostscript	210
Troubleshooting	211
Error Messages	211
SA_REPORT_QUEUE Table	213
Limitations	214
Document Control Module.....	215
Fields	215
Sequence No.: Document ID	215
Code Tables	215
Code Table 409: Document Classifications Codes	215
Code Table 276: Document Media Types	215
Code Table 410: Document File Types	215
Copy Record	215
DOCUMENT - COPY RECORD	215
Functions	215
Document to Active	216
MSDS Module.....	217
Copy Record	217
MSDS - COPY RECORD	217
Chemical Label Module.....	217
Copy Record	217
MSDSCHEM - COPY RECORD	217
Specification Module.....	218
Reports	218
S_RPT005 - Specification Report	218
Specification Template Module.....	218
Fields	218
Sequence No.: Specification ID	218
Code Tables	218
Code Table 37: Specification Types	218
Linked Code Table (i.e.101): Specification Category Codes	218

Views	219
Specification Configuration	219
Standard Notes Module	220
Fields	220
Sequence No.: Standard Notes ID	220
Code Tables	220
Code Table 91: Standard Note Types	220
Copy Record	220
STDNOTES - COPY RECORD	220
Procedure Module	221
Fields	221
Sequence No.: Procedure No.	221
Code Tables	221
Code Table 16: Procedure Types	221
Code Table 28: Procedure Categories	221
Code Table 29: Asset Type	221
Business Rules	222
Procedure Attachment Update	222
Procedures Authority Rule	223
Copy Record	223
PROCEDUR - COPY RECORD	223
Functions	223
Add/Delete Job Hazard	224
Create New Procedure Revision	224
Modify Job Hazard	224
Reports	224
S_RPT003 - Procedures Report	224
Job Hazard Module.....	225
Fields	225
Sequence No.: Hazard ID	225
Code Tables	225
Code Table 470: Job Hazard Type	225
Code Table 471: Job Hazard Category	225
Code Table 472: Protective Equipment	225
Copy Record	225
JOBHZRD - COPY RECORD	225
Functions	225
Revise Procedure	225
Function Module.....	226
Fields	226
Sequence No.: Function ID	226
Code Tables	226
Code Table 137: Function Types	226
Code Table 110: Backlog Group	226
Copy Record	226
FUNCTION - COPY RECORD	226
Process Module.....	227
Fields	227
Maintenance Manager Field	227
Planner Field	227
Maintenance and Production Approver Fields	227
Department, Area, and Account Fields	227
Fixed Asset Field	227
Code Tables	227
Code Table 138: Process Types	227
Code Table 25: Building Codes	227
Code Table 110: Backlog Groups	227
Code Table 231: Location	228
Business Rules	228
Planner Rule	228
Functions	228

Create Work Order Process	229
Create Work Request Process	229
Copy Record	229
PROCESS - COPY RECORD	229
Reports	229
S_RPT006 - Process Report	229
S_RPT007 - Process Report with Asset Detail	229
Maintenance Manager Module	230
Copy Record	230
MAINTMGR - COPY RECORD	230
Keys and Locks Module.....	230
Code Tables	230
Code Table 515: Set Category (User)	230
4 Maintenance Subsystem	231
Work Request Module.....	231
Fields	231
Sequence No.: Work Request No.	231
Approval Route Field	231
Business Rules	232
Batch Purge Criteria Rule	232
Batch Purge Parameters Rule	233
Criticality Override Rule	234
Default Backlog Groups Rule	234
Default Work Request Req Date Rule	235
Planner Rule	236
Work Request Processing Rule	238
Batch Processes	238
Purge Work Requests - sdbp_purge_work_requests;	238
Code Tables	238
Code Table 10: Failure Codes (Length = 10)	238
Code Table 110: Backlog Group (Length = 6)	239
Code Table 25: Building Codes (Length = 20)	239
Code Table 2: Maintenance Classes (Length = 10)	239
Code Table 3: Maintenance Categories (Length = 10)	239
Code Table 40: Criticality Codes (Length = 1)	239
Code Table 41: Work Priority Codes (Length = 1)	239
Code Table 139: Downtime Codes (Length = 10)	239
Copy Record	239
WORKREQ - COPY RECORD	239
Functions	239
Create Work Request	240
Create Work Request Asset	240
Create Work Request Component	240
Create Work Request Fleet Asset	240
Create Work Request Process	240
Reports	240
S_RPT042 - Work Request Summary Report	240
Work Design Module.....	241
Fields	241
Sequence No.: Work Design No.	241
Approval Route Field	241
Business Rules	242
Compatible Unit Function Rule	242
PO Report Constants Rule	242
Work Design Phase Rule	243
Work Design Processing Rule	243
Code Tables	243
Code Table 22: Vendor Characteristic Types (Characteristics View)	243
Code Table 23 - Units for length (Length = 4)	244

Code Table 159: Federal Tax Codes (Buyer Data View) (Length = 1)	244
Code Table 160: State Tax Codes (Buyer Data View) (Length = 1)	244
Code Table 161: Duty Codes (Buyer Data View) (Length = 1)	244
Code Table 730: Contribution in Aid to Construction (Length = 30)	244
Code Table 731: Work Design Cost Type (Length = 30)	244
Code Table 732: Location Structure Type (Length = 30)	244
Functions	244
UPDATE PRICING FOR WD	244
CREATE WO FROM WORK DESIGN	244
ROUTE TO DESIGNER	244
Reports	244
S_RPT154 - Work Design	244
S_RPT156 - Work Design Comparison	244
S_RPT155 - Work Design Estimate	244
Copy Record	245
WODESIGN- COPY RECORD	245
Work Order Module	246
Fields	246
Sequence No.: Work Order No.	246
Approval Route	246
Business Rules	247
Alerts Rule	247
Batch Purge Criteria Rule	248
Batch Purge Parameters Rule	249
Planner Rule	250
S_RPT071 Crew Craft Columns Rule	251
Work Order Aging Rule	251
Work Order Processing Rule	251
Work Priority Defaults Rule	252
Batch Processes	252
Close Work Order - sdbp_close_work_orders;	252
Held for Parts - sdbp_held_for_parts;	252
PM Cycle - sdbp_pm_cycle_job.start_job;	252
Process Service Timesheet - sdbp_process_service_timesheet.post_approved_time;	252
Purge Work Order - sdbp_purge_work_order.purge_wo;	253
Purge Work Requests - sdbp_purge_work_requests;	253
Finish WO - sdbp_finish_wo;	253
PM Finish - sdbp_pm_finish;	253
Reset Demand Quantity - sdbp_storeroom_demand;	253
Code Tables	253
Code Table 2: Maintenance Classes (Length = 10)	253
Code Table 3: Maintenance Categories (Length = 10)	253
Code Table 41: Work Priority (Length = 1)	253
Code Table 110: Backlog Group (Length = 6)	253
Code Table 120: Crew Event Types (Length = 15)	254
Functions	254
Activate WO Material	254
Add Customer Contributed	254
Allow WO Project Update	254
Create Emergency Work Order	254
Create Emergency WO Fleet Asset	254
Create Emergency WO Asset	254
Create Permit From WO	254
Create WO From Benchmark	254
Create Work Order	254
Create Work Order Process	254
Create Work Order Fleet Asset	254
Create Work Order Component	254
Create Work Order Asset	255
Reconcile CU	255
Repair Removed Part	255
Search Duplicate Permits	255
Show CU Location	255
Show CU on WO	255
Update Benchmark Work Order	255

Update Process on Work Order	255
Update WO from Benchmark	255
WO Active to Planning	255
WO Closed to Finished	255
WO Finished to Active	255
WO Finished to Closed	255
WO to Active	255
Work Type Update	255
Charts	256
S_CHT123 - Actual Cost to Planning Estimate	256
S_CHT124 - Corrective vs. Preventive Work Orders	256
S_CHT145 - Emergency Work Orders	256
S_CHT122 - Planning Accuracy	256
S_CHT146 - Preventive Maintenance Investment	256
S_CHT151 - Work Order Aging	256
Metrics	256
S_MTRC5 - Percent Preventive Work - sdbp_metric_pct_pm_wos	256
S_MTRC10 - Percent PM Investment - sdbp_metric_pct_pm_investment	256
S_MTRC7 - Percent Emergency Work - sdbp_metric_pct_emergency_wos	256
Reports	257
S_RPT046 - Work Order Aging Report	257
S_RPT091 - Historic Cost Performance by Asset Report	257
S_RPT078 - Holiday Overtime Standing Report	257
S_RPT026 - Inventory Picklist Report	257
S_RPT048 - Work Order (Condensed) Report	257
S_RPT071 - Work Order Forecast Report	257
S_RPT044 - Work Order Package Report	257
Work Order Task Module	258
Business Rules	258
Credit Card Purchases Rule	258
Criticality Override Rule	258
Default Backlog Groups Rule	259
Planner Rule	259
PM Route Options Rule	260
Validate Task Report Codes Rule	261
Variable Expense Codes Rule	261
Work Order Processing Rule	263
Work Order Task Planning Rule	267
Work Order Travel Time Rule	267
Code Tables	267
Code Table 12: Shop Codes	267
Code Table 41: Work Priority	268
Code Table 107: Units	268
Code Table 190: Job Codes	268
Code Tables 281 - 285: Report Codes 1-5	268
Code Table 660: Vehicle Reason for Repair	268
Code Table 661: Vehicle Action Taken	268
Code Table 662: Vehicle System Codes	268
Code Table 1050: Precedence Relationship Code	268
Work Order (Finishing Tasks)	268
Code Table 9: Repair Codes (Length = 10)	268
Code Table 10: Failure Codes (Length = 10)	269
Code Table 51: Failure Modes (Length = 10)	269
Code Table 52: Root Cause Codes (Length = 10)	269
Code Table 189: Work Action Codes (Length = 8)	269
Code Table 222: Component Category (Length = 10)	269
Functions	269
Add Dependent Materials	269
Assign Contractor to CUs	269
Cost and Closeout	269
Create Checkout Request from WO	269
Repair Removed Part	269
Show CU Location	270
Show CU on WO	270
Update Reg Acct. Dist	270

Value Assets in Prior Year	270
WO Task to Active	270
Reports	270
S_RPT056 - Work Order Task Aging Report	270
S_RPT041 - Daily Schedule Report	270
S_RPT040 - Workweek Schedule Report	270
S_RPT045 - Work Order Backlog Report	270
S_RPT055 - Work Order Backlog Detail Report	270
S_RPT043 - Work Order Tasks Delayed by Materials Report	270
Batch Processes	270
Cost Asset - sdbp_cost_asset;	270
Cost Adjustment for PM Route - sdbp_cost_route.cost_route;	271
Cost and Closeout - smu_interface.sdbp_mu_interface;	271
Cost Labor - sdbp_cost_labor.cost_labor;	271
Create Change Request - sdbp_create_change_request.create_change_req_from_wo;	271
Finish WO - sdbp_finish_wo;	271
Held for Parts - sdbp_held_for_parts;	271
Process Fixed Assets - sdbp_work_order.fixed_asset;	271
Process Service Timesheet - sdbp_process_service_timesheet.post_approved_time;	271
Reschedule - sdbp_reschedule.job_reschedule;	271
Reset Demand Quantity - sdbp_storeroom_demand;	271
Regulatory Account Cost - sdbp_regulatory_account_cost;	272
Work Order Labor - sdbp_work_order_labor;	272
Benchmark Work Order Module.....	273
Fields	273
Sequence No.: Benchmark Work Order No.	273
Batch Processes	273
PM Cycle - sdbp_pm_cycle_job.start_job;	273
Work Order Labor - sdbp_work_order_labor;	273
Copy Record	274
BENCHWO - COPY RECORD	274
Functions	274
Create Work Order From Benchmark	274
Crew Module	275
Fields	275
Crew Field	275
Business Rules	275
Auto Generate Daily Schedule Rule	275
Craft Rates Rule	276
Code Tables	276
Code Table 310: Supervisor Title	276
Copy Record	276
CREWMOD - COPY RECORD	276
Reports	276
S_RPT079 - Overtime Standing Report by Crew	276
Views	277
Crew Daily Hours	277
Crew Employee Assignment	277
Crew Activity Log Module.....	278
Fields	278
Crew	278
Code Tables	278
Code Table 110: Backlog Groups	278
Code Table 120: Crew Event Types	278
Activity Tracking Module	279
Fields	279
Sequence No.: Tracking No.	279
Code Tables	279
Code Table 13: Type of Activity	279
Code Table 14: Type of Activity Units	279
Copy Record	279
ACTTRACK - COPY RECORD	279

Fleet Asset Module.....	280
Fields	280
Sequence No.: Vehicle ID	280
Class	280
Specification (More Data View)	280
Operational ID (Fleet Operational/Maintenance View)	280
Maintenance Manager	280
Business Rules	281
Asset Depreciation Rule	281
Asset Key Segments Rule	282
Downtime Type By Work Type	283
Fleet Constants Rule	283
Fleet Mileage Reasonability Rule	284
Planner Rule	285
Batch Processes	285
Depreciate Assets - sdbp_end_period_depreciation;	285
Code Tables	285
Code Table 38: Drive Types (More Data View)	285
Code Table 39: Fuel Types (More Data View)	285
Code Table 40: Criticality Codes	285
Code Table 12: Shop Codes	286
Code Table 25: Building Codes	286
Code Table 67: Vehicle Make	286
Code Table 510: Vehicle Organization	286
Code Table 511: Vehicle Sub-Organization	286
Code Table 512: Monitoring Group (Fleet Operational/Maintenance View)	286
Vehicle Model Code Tables	286
Copy Record	286
FLTASSET - COPY RECORD	286
Functions	286
Create Activity Log From Asset	287
Create Emergency WO Fleet Asset	287
Create Work Order Fleet Asset	287
Create Work Request Fleet Asset	287
Reports	287
S_RPT075 - Equipment History Summary Report	287
S_RPT077 - Equipment List by Shop Report	287
S_RPT076 - Historical Cost Performance Report	287
S_RPT073 - Mechanic Accountability Report	287
Fleet Work Order Module.....	288
Fields	288
Sequence No.: Fleet Work Order No.	288
Code Tables	288
Code Table 3: Maintenance (Length = 10)	288
Code Table 2: Maintenance Classes (Length = 10)	288
Code Table 12: Shop Codes (Length = 10)	288
Code Table 41: Work Priority Codes (Length = 1)	288
Code Table 107: Meter Units (Length = 15)	288
Functions	288
Create Checkout Request from WO	289
Log Fleet Downtime	289
Repair Removed Part	289
Update Benchmark Work Order	289
Update WO from Benchmark	289
Fleet Work Order Task Module.....	290
Fields	290
Permit Types LOV (Work Order Permit View)	290
Code Tables	290
Code Table 190: Job Codes (Length = 10)	290
Code Table 281 - 285: Report Codes 1 - 5 (Length = 10)	290
(Optional) Code Table 660: Vehicle Reason for Repair (Length = 10)	290
Code Table 661: Vehicle Action Taken (Length = 10)	290
Code Table 662: Vehicle System (Length = 3)	290
Code Table 1150: Vehicle Assembly (Length = 3)	290

Code Table 1151: Vehicle Component (Length = 3)	290
Fleet Benchmark Work Order Module	291
Fields	291
Sequence No.: Fleet Benchmark Work Order	291
BENCHFLT- COPY RECORD	291
Reservations/Motorpool Module	292
Fields	292
Sequence No.: Reservation No.	292
Code Tables	292
Code Table 24: Rental Types (Length = 10)	292
Reports	292
S_RPT072 - Reservation Dispatch Report	292
Operational Schedule Module	293
Fields	293
Sequence No.: Operational ID	293
Code Tables	293
Code Table 570: Hour	293
Code Table 571: Minute	293
Code Table 710: Week Days	293
Copy Record	293
OPERSCHD - COPY RECORD	293
Permit Template Module	294
Fields	294
Sequence No.: Template ID	294
Code Tables	294
Checklist Title - User Defined Code Table	294
Checklist Description - User Defined Code Table	294
Duration - User Defined Code Table	294
Copy Record	295
PERMTMPL - COPY RECORD	295
Permits Module	296
Fields	296
Sequence No.: Permit No.	296
Approval Route Field	296
Code Tables	296
Code Table 8: Permit Cancel Codes (Length = 10)	296
Code Table 62: Current Position	296
Business Rules	297
Permit Type Rule	297
Permit Processing Rule	298
Attachment Printing Rule	298
Copy Record	299
PERMIT - COPY RECORD	299
Functions	299
Add Tag Points	299
Permit to Active	299
Release All	299
Tag All	299
Verify All	299
Reports	299
S_RPT098 - Confined Space Report	299
S_RPT101 - Confined Space Report [Blank]	299
S_RPT099 - Hot Work Permit Report	299
S_RPT102 - Hot Work Permit Report [Blank]	299
S_RPT113 - Lockout Tagout Report	300
S_RPT100 - Safety Work Permit Report	300
Tag Point Module	301
Fields	301
Sequence No.: Tracking No.	301
Code Tables	301
Code Table 1193: Tag Point Category	301

Code Table 25: Building Codes	301
Code Table 61: Source Type	301
Code Table 62: Positions for Isolation	301
Business Rules	302
Permit Type Rule	302
Copy Record	302
TAGPOINT - COPY RECORD	302
Functions	303
Create Tag List	303
Tag List Module	304
Fields	304
Sequence No.: Tracking No.	304
Copy Record	304
TAGLIST- COPY RECORD	304
Functions	304
Associate Tag List	304
PM Master Module	305
Fields	305
Sequence No.: PM Master No.	305
Code Tables	305
Code Table 198: PM Categories	305
Code Table 107: Units	305
Code Table 108: Event Groups	305
Code Table 109: Event Types	305
Business Rules	306
Default Backlog Groups Rule	306
PM Master Parameters Rule	306
PM Schedule Basis Rule	308
PM Seasonal Adjustments Rule	309
Batch Processes	309
PM Cycle - sdbp_pm_cycle_job.start_job;	309
PM Finish - sdbp_pm_finish;	309
PM Routing - sdbp_pm_routing;	309
Copy Record	309
PMMASTER- COPY RECORD	309
Functions	310
Cancel PM Master Backlog	310
Credit PM	310
Show Cycle This PM Now Action	310
Show Cycle PM Group Now Action	310
Update Estimate Hours	310
Update Estimate Quantity	310
Reports	310
S_RPT090 - PM By Asset Report	310
S_RPT074 - Preventive Maintenance Report	310
Charts	310
S_CHT124 - Corrective vs. Preventive Work Orders	310
S_CHT142 - Late PMs for Safety Equipment	310
S_CHT143 - Late Preventive Maintenance Work Orders	310
S_CHT164 - PM Forecast Months	311
S_CHT129 - PM Forecast Months - Estimated Duration	311
S_CHT130 - PM Forecast Weeks	311
S_CHT165 - PM Forecast Weeks - Estimated Duration	311
S_CHT131 - PM History Months	311
S_CHT132 - PM History Weeks	311
S_CHT146 - Preventive Maintenance Investment	311
S_CHT147 - Preventive Work Orders	311
Metrics	311
S_MTRC5 - Percent Preventive Work - sdbp_metric_pct_pm_wos	311
S_MTRC10 - Percent PM Investment - sdbp_metric_pct_pm_investment	311
S_MTRC8 - Late PMs for Safety Equipment - sdbp_metric_late_pms_safety	312
S_MTRC9 - Late PMs - sdbp_metric_late_pm	312
PM Event Module	313

Code Tables	313
Code Table 108: Event Groups	313
Code Table 109: Event Types	313
Copy Record	313
PMEVENT - COPY RECORD	313
FMEA Template Module	314
Fields	314
Sequence No.: FMEA Template ID	314
Business Rules	314
FMEA Template RPN Defaults Rule	314
Code Tables	315
Code Table 9: Repair Codes (Length = 10)	315
Code Table 10: Failure Codes (Length = 10)	315
Code Table 51: Failure Modes (Length = 10)	315
Code Table 52: Root Cause Codes (Length = 10)	315
Code Table 189: Work Action Codes (Length = 8)	315
Code Table 344: FMEA System Code	315
Functions	315
Create FMEA Failure Item	315
Create FMEA PM Control	315
.....	315
Asset PM Control.....	316
Fields	316
Sequence No.: Control No.	316
Class	316
Code Tables	316
Code Table 67: Vehicle Make (Length = 10)	316
Vehicle Model Code Tables	316
Code Table 344: FMEA System Code	316
Business Rules	317
PM Control Types Rule	317
Copy Record	317
FLEETPMC - COPY RECORD	317
PM Route Module	319
Business Rules	319
PM Route Options Rule	319
Code Tables	319
Code Table 20: PM Route Types	319
Code Table 49: PM Route Task Types (Route Stops View)	319
Code Table 44: Lube Types (Route Stops View)	319
Code Table 42: Lube Methods (Route Stops View)	319
Batch Processes	319
Cost Adjustment for PM Route - sdbp_cost_route.cost_route;	319
PM Routing - sdbp_pm_routing;	320
Copy Record	320
PMROUTE - COPY RECORD	320
Reports	320
S_RPT058 - PM Route Report	320
Project/Subproject Module	321
Fields	321
Sequence No.: Project ID	321
Approval Route Field	321
Code Tables	321
Code Table 310: Supervisor Title	321
Copy Record	321
PROJECT - COPY RECORD	321
Business Rules	322
Account Creation from Projects Rule	322
Project Budget Options Rule	323
Project Management Rule	325
Project Work Order Account Rule	326
Work Order Processing Rule	327

Functions	327
Allow WO Project Update	327
Project Closed to Finished	327
Project Finished to Closed	327
Project Management	327
Subproject Approved to Created	327
Subproject Finished to Approved	328
Batch Processes	328
Project Alert - sdbp_project_alert;	328
Charts	328
S_CHT149 - Project Analysis	328
Views	328
Subproject	328
Microsoft Project Interface	328
Project Management Configuration	328
Runtime Entry Module	330
Code Tables	330
Code Table 107: Meter Units	330
Business Rules	330
Asset Runtime Rule	330
Daily Schedule Module	331
Business Rules	331
Auto Generate Daily Schedule Rule	331
Default Backlog Groups Rule	332
Work Week Rule	332
Scheduling Options Rule	333
Code Tables	333
Code Table 1190: Daily Schedule Types	333
Code Table 2501: Interruption Codes	333
Batch Processes	333
Reschedule - sdbp_reschedule.job_reschedule;	333
PM Cycle - sdbp_pm_cycle.job.start_job;	333
Functions	334
Activate Checkout Request from Schedule	334
Merge Task WOWeek to Day Schd	334
Reports	334
S_RPT152 - Daily Schedule Assignments Report	334
S_RPT041 - Daily Schedule Report	334
Installation Parameters	334
SCHEDULING TOTAL EST HRS DISP	334
Workweek Schedule Module	335
Business Rules	335
Auto Generate Weekly Schedule Rule	335
Default Backlog Groups Rule	336
Work Week Rule	336
Code Tables	337
Code Table 2500: Daily Schedule Types	337
Code Table 2501: Interruption Codes	337
Batch Processes	337
Reschedule - sdbp_reschedule.job_reschedule;	337
PM Cycle - sdbp_pm_cycle.job.start_job;	337
Functions	337
Merge Task WOWeek to Day Schd	337
Installation Parameters	337
SCHEDULING TOTAL EST HRS DISP	337
Schedule Plan Module	338
Business Rules	338
Work Week Rule	338
Reports	338
S_RPT153 - Schedule Plan Report	338
Direct Charges Module	339

Fields	339
Sequence No.: Direct Charges No.	339
Approval Route Field	339
Owner Field	339
Code Tables	339
Code Table 550: Direct Charge Category Codes	339
Business Rules	340
Direct Charge Types Rule	340
Batch Processes	340
Direct Charges - sdbp_direct_charges.direct_charges;	340
Cost and Closeout - smu_interface.sdbp_mu_interface (job_in, plant_in,'N');	341
Copy Record	341
ODC - COPY RECORD	341
Functions	341
Cost and Closeout	341
Leave Request Module.....	342
Business Rules	342
Timekeeping Authority Rule	342
Timekeeping Leave Types Rule	343
Code Tables	344
Code Table 48: Leave Reason Codes	344
Copy Record	344
LEAVEREQ - COPY RECORD	344
Batch Processes	344
Leave Request - sdbp_post_leave;	344
Create New Leave Year sdbp_create_new_leave_year.new_leave_year;	344
Reports	344
S_RPT065 - Employee Pay Period Time Report	344
Payroll Voucher Module.....	345
Business Rules	345
Payroll Voucher Types Rule	345
Batch Processes	345
Payroll Voucher - sdbp_pay_voucher.pay_voucher;	345
Timekeeping Module	346
Fields	346
Next Approver Field	346
Code Tables	346
Code Table 310: Supervisor Title	346
Business Rules	346
Craft Rates Rule	346
Holidays Rule	346
Labor Burden Multipliers Rule	347
Labor Costing Markup Rule	348
Labor Costing Wage Rates Rule	348
Overtime Standings Rule	349
Scheduled Holidays	349
Shift Differential Rates Rule	350
Timekeeping Authority Rule	351
Timekeeping Charge Types Rule	352
Timekeeping Comp Time Request Rule	353
Timekeeping Copy Options Rule	353
Timekeeping Editchecks Rule	354
Timekeeping Labor Earning Type Rule	354
Variable Expense Codes Rule	356
Copy Record	357
TIMESHT - COPY RECORD	357
Functions	357
Approve All Timesheets	357
Cost and Closeout	357
Route Timesheet for Approval	357
Timesheet Wizard	358
Batch Processes	358
Auto Create Timesheets - sdbp_auto_create_timesheet.main;	358

Cost and Closeout - smu_interface.sdbp_mu_interface (job_in, plant_in,'N');	358
Leave Request - sdbp_post_leave;	358
Post Timesheet - sdbp_post_timesheets.post_time;	358
Reports	358
S_RPT066 - Payroll Report	358
S_RPT067 - Labor Expenditure Summary by Account Report	358
S_RPT068 - Labor Distribution by Account Report	358
S_RPT069 - Labor Distribution by Employee Report	358
S_RPT079 - Overtime Standing Report by Crew	358
S_RPT080 - Overtime Standing Report by Zone	358
S_RPT139 - Employee Timekeeping Report	358
Charts	358
S_CHT138 - Timekeeping Analysis	358

5 Purchasing Subsystem 359

Vendor Code Structure Module..... 359

Fields	359
Segment Name	359
Length	359
Sequenced?	359
Required	360
Delimiter Character	360

Vendor Module..... 360

Fields	360
Sequence No.: Vendor Code	360
E-Mail Purchase Orders to Vendors (Characteristics View)	360
Business Rules	361
Payment Terms Rule	361
Vendor Options Rule	362
Vendor Performance Attributes Rule (Performance View)	363
Vendor Performance Ranges Rule (Performance View)	364
Code Tables	364
Code Table 22: Vendor Characteristic Types (Characteristics View)	364
Code Table 43: FOB	364
Code Table 56: Vendor Characteristics (Characteristics View)	364
Code Table 68: Vendor Classification Types (Characteristics View)	364
Code Table 122: Commodity Category Codes (Commodities View)	364
Code Table 123: Commodity Composition (Commodities View)	365
Code Table 115: Auditor Codes (Approved Vendors View)	365
Code Tables 173, 174, 177, 178, and 179: Vendor Capability Code Segments 1-5 (Capabilities View)	365
Code Table 175: Vendor Evaluation Grades (Evaluation View)	365
Code Table 65: Purchasing Vendor Characteristics (Characteristics View)	365
Copy Record	365
VENDOR - COPY RECORD	365
Functions	366
Set Vendor Auto Pay Indicator	366
Batch Processes	366
Vendor Performance - sdbp_vendor_performance.vendor_performance;	366
Charts	366
S_CHT1136 - PO By Vendor - Count of POs	366
S_CHT135 - PO By Vendor - Total Amount	366
Reports	366
S_RPT142 - Deficient Vendors Report	366
S_RPT201 - Purchase Order Listing Report - Grouped by Vendor Code	366
S_RPT207 - Purchase Order Report - Vendor Copy	366
S_RPT200 - Purchase Order Vendor Report	366
S_RPT018 - Storeroom Value by Vendor	367
S_RPT143 - Superior Vendor Performance Data	367
S_RPT022 - Vendor Characteristics Report	367
S_RPT213 - Vendor Classification Activity Report	367
S_RPT124 - Vendor Label Report	367
S_RPT021 - Vendor Listing Report	367

S_RPT144 - Vendor Performance by Buyer	367
S_RPT145 - Vendor Performance Data	367
S_RPT141 - Vendors with 3 or More Deficiencies	367
Requisition Module	368
Fields	368
Sequence No.: Requisition Number	368
Approval Route Field	368
Buyer field	368
Ship To field	368
Currency (Buyer Data View)	368
Business Rules	369
Alerts Rule	369
Batch Purge Criteria Rule	370
Batch Purge Parameters Rule	371
Credit Card Purchases Rule	372
Requisition to PO Rule	372
Purchasing Options Rule	373
Code Tables	375
Code Table 7: Location (Length = 10)	375
Code Table 23: Unit of Measure (Line Item (Detail) View) (Length = 4)	375
Code Table 26: End Use Code (Buyer Data View) (Length = 2)	375
Code Table 43: FOB (Buyer Data View)	375
Code Table 159: Federal Tax Codes (Buyer Data View) (Length = 1)	375
Code Table 160: State Tax Codes (Buyer Data View) (Length = 1)	375
Code Table 161: Duty Codes (Buyer Data View) (Length = 1)	375
Functions	375
Create Req from Blanket	375
Create Shipping Memo	375
Create Templates from REQ	375
Resend Approval Request	375
Batch Processes	376
Purge Requisitions - sdbp_purge_requisitions;	376
Requisition Template Status Check - sdbp_req_template_status_chk;	376
Metrics	376
S_MTRC3 - Total Lead Time - sdbp_metric_total_lead_time	376
Reports	376
S_RPT054 - Requisition Report	376
S_RPT215 - Requisition Report (by Vendor)	376
Purchase Order Module	377
Fields	377
Sequence No.: Purchase Order	377
Approval Route Field	377
Buyer field	377
Ship To field	377
Currency (Buyer Data View)	377
User-Defined	377
Business Rules	378
Alerts Rule	378
Batch Purge Criteria Rule	379
Batch Purge Parameters Rule	380
Credit Card Purchases Rule	381
PO Aging Rules Rule	381
PO Report Constants Rule	382
PO Report Status Codes Rule	383
Purchasing Options Rule	384
Code Tables	385
Code Table 7: Location (Length = 10)	385
Code Table 23: Unit of Measure (Line Item (Detail) View) (Length = 4)	386
Code Table 26: End Use Code (Buyer Data View) (Length = 2)	386
Code Table 43: FOB (Buyer Data View) (Length = 20)	386
Code Table 150: Confirmation Types (Buyer Data View) (Length = 10)	386
Code Table 154: Expediting Item Status (Expedite View, Expedite Items Detail) (Length = 15)	386
Code Table 159: Federal Tax Codes (Buyer Data View) (Length = 1)	386
Code Table 160: State Tax Codes (Buyer Data View) (Length = 1)	386

Code Table 161: Duty Codes (Buyer Data View) (Length = 1)	386
Functions	386
Change PO Auto Pay Indicator	386
Copy PO from PO	386
Transfer Canceled PO Items	386
Resend Approval Request	386
Batch Processes	387
Purge Requisitions - sdbp_purge_requisitions;	387
Vendor Performance - sdbp_vendor_performance;	387
Check Received PO Item - sdbp_chk_issd_po_item;	387
PO Closeout - sdbp_po_closeout;	387
Charts	387
S_CHT133 - PO By Buyer - Total Amount	387
S_CHT134 - PO By Buyer - Count of POs	387
S_CHT135 - PO By Vendor - Total Amount	387
S_CHT1136 - PO By Vendor - Count of POs	387
Metrics	387
S_MTRC2 - Internal Time to Issue PO - sdbp_metric_int_time_to_issue	387
S_MTRC3 - Total Lead Time - sdbp_metric_total_lead_time	388
S_MTRC4 - External Time to Receive Parts - sdbp_metric_ext_time_rec_part	388
Reports	388
S_RPT105 - Accruals By Account Report	388
S_RPT214 - Contract PO Activity Report	388
S_RPT107 - Delivery Receiving Report	388
S_RPT027 - Delivery Ticket Report	388
S_RPT212 - Open Purchase Orders Detail Report	388
S_RPT211 - Open Purchase Orders Summary Report	388
S_RPT024 - Purchase Order Accruals (Unpaid Receipts) Report	388
S_RPT062 - Purchase Order Accruals (Unpaid POs) Report	388
S_RPT204 - Purchase Order Expensing Account Detail Report	388
S_RPT202 - Purchase Order Inventory Item Cost Report	388
S_RPT203 - Purchase Order Listing Report - Grouped by PO Number	388
S_RPT201 - Purchase Order Listing Report - Grouped by Vendor Code	388
S_RPT029 - Purchase Order Over Received Report	388
S_RPT208 - Purchase Order Report - Department Copy	388
S_RPT209 - Purchase Order Report - Finance Copy	389
S_RPT207 - Purchase Order Report - Vendor Copy	389
S_RPT200 - Purchase Order Vendor Report	389
S_RPT053 - Purchase Order Report	389
S_RPT112 - Purchase Order Report with Standard Notes and Attachments	389
S_RPT023 - Purchase Orders Not Yet Received Report	389
S_RPT010 - Purchase Orders with Returns Report	389
S_RPT063 - Ready for Payment Report	389
S_RPT025 - Receiving Report	389
S_RPT216 - Receiving Report	389
S_RPT037 - Receiving Worksheet Report	389
Change Order Module	390
Fields	390
Approval Route Field	390
Business Rules	390
C.O. Auto Approve Percentage Rule	390
Purchasing Options Rule	391
Functions	391
Resend Approval Request	391
Blanket Contract Module	392
Fields	392
Sequence No.: Blanket Contract No.	392
Business Rules	392
Attachment Drive Mapping Rule	392
Multiple Active Contracts Rule	393
Blanket Contract Processing Rule	393
Blanket Contract Access List Rule	394
Purchasing Options Rule	395
Code Tables	396

Code Table 35: Blanket Contract Category Codes	396
Copy Record	397
BLNKTCN - COPY RECORD	397
Functions	397
CREATE BLANKET CONTRACT REVS	397
CREATE BLNKET CONTRACT REV HIST	397
DUPLICATE BLANKET TO PO	397
Batch Processes	397
Auto Activate Blankets - sdbp_blanket_services.auto_activate;	397
Auto Close Blankets - sdbp_blanket_services.auto_close;	397
Reports	397
S_RPT206 - Blanket Contract Report	397
Request for Quotes Module.....	398
Fields	398
Sequence No.: Request for Quotes	398
Next Approver Field	398
Business Rules	398
Default Directories Rule	398
Vendor Performance Ranges Rule	399
Code Tables	400
Code Table 17: Issue Methods (Vendor (Detail) View)	400
Copy Record	400
RFQ - COPY RECORD	400
Functions	400
Add Vendor After RFQ Issued	400
Award RFQ	400
Export RFQ	400
Import RFQ	400
Issue RFQ	400
Reports	401
S_RPT093 - Request for Quotes Report	401
Invoicing Module	402
Fields	402
Approval Route Field	402
Business Rules	402
Federal Tax Rebate Rule	402
Invoice Setup Criteria Rule	403
Invoice Prorate Defaults Rule	405
Invoice Tolerances Rule	406
Payment Terms Rule	407
Purchasing Options Rule	408
Custom LOV Notes for the Invoicing Module	408
Functions	408
Display Accrual Tax Total	408
Invoice Account Override	408
Invoice - Override Discrepant	409
Invoice - Resolve Discrepant	409
Invoice Pay to Vendors	409
Code Tables	409
Code Table 159: Federal Tax Codes (Length = 1)	409
Code Table 160: State Tax Codes (Length = 1)	409
Code Table 161: Duty Codes (Length = 1)	409
Code Table 157: Invoice Prorate Options	409
Batch Processes	409
Invoice Resolution - sdbp_invoice-resolution;	409
Cost Invoice - sdbp_cost_invoice.cost_invoice;	409
Automatic Invoicing - sdbp_ers_invoicing;	409
Reports	409
S_RPT064 - Invoice Variance Report	409
S_RPT024 - Purchase Order Accruals (Unpaid Receipts) Report	409
Invoice Batch Module.....	410
Fields	410
Sequence No.: Batch ID	410

Code Tables	410
Code Table 243: Process Level	410
Warranty Claim Module.....	411
Fields	411
Sequence No.: Warranty No.	411
Functions	411
CREATE WARRANTY CLAIM	411
Batch Processes	411
Warranty Expiration Alerts - sdbp_process_warranty_alerts;	411
Warranty Module	412
Fields	412
Sequence No.: Warranty No.	412
Business Rules	412
Warranty Processing Rule	412
Functions	412
CREATE WARRANTY CLAIM	413
Copy Record	413
WARRANTY - COPY RECORD	413
Batch Processes	413
Warranty Expiration Alerts - sdbp_process_warranty_alerts;	413
Cost Adjustment Module	414
Fields	414
Sequence No.: Adjustment ID	414
Next Approver Field	414
Business Rules	414
Cost Adjustments Rule	414
Batch Processes	415
Asset Cost Allocation - sdbp_cost_asset;	415
Cost Adjustment for PM Route - sdbp_cost_route.cost_route;	415
Cost Adjustment - sdbp_cost_adjustment;	415
Purchasing Log Module.....	416
Code Tables	416
Code Table 121: Purchasing Event Types	416
Blanket Contract Log Module.....	416
Service Contract Module	417
Fields	417
Sequence No.: Contract	417
Code Tables	417
Code Table 35: Contract Category Codes	417
Copy Record	417
SERVCONTR - COPY RECORD	417
Reports	417
S_RPT087 - Service Contract Accrued Cost Report	417
S_RPT085 - Service Contract Details Report	417
S_RPT086 - Service Contract Summary Report	417
Service Contract Invoice Module	418
Code Tables	418
Code Table 700: Job Reference Codes	418
Business Rules	418
Serv Invoice Account Override Rule	418
Serv Invoice Prorate Defaults Rule	419
Serv Invoice Tolerances Rule	420
Functions	420
Serv Invoice Account Override	420
Service Invoice Export Wizard	420
Batch Processes	420
Cost Service Invoice - sdbp_cost_service_invoice.cost_service_invoice;	420
Accumulate Posted Service Timesheets - sdbp_process_service_timesheet.accumulate_posted;	420
Service Contract Timesheets Module.....	421

Business Rules	421
Service Timesheet Charge Types Rule	421
Code Tables	421
Code Table 700: Job Reference Codes	421
Copy Record	421
CTIMESHT - COPY RECORD	421
Functions	422
Copy Service Timesheet	422
Copy to New Service Contract	422
Service Contract to Active	422
Batch Processes	422
Process Service Timesheet - sdbp_process_service_timesheet.post_approved_time;	422

6 Inventory Subsystem 423

Checkout Request Module 423

Business Rules	423
Alerts Rule	423
Bar Code Configuration Rule	424
Checkout Request Rule	424
Storeroom Demand Allocation Rule	426
Variable Expense Codes Rule	427
Code Tables	428
Code Table 7: Deliver To Location (Length = 10)	428
Code Table 100: Checkout Request Priority (Length = 2)	428
Copy Record	428
CHKREQST - COPY RECORD	428
Functions	429
Add Items From Work Order	429
Activate Checkout Request from Schedule	429
Reports	429
S_RPT026 - Inventory Picklist Report	429

Stock Checkout Module 430

Business Rules	430
Checkout Allowable Charge Type Rule	430
Checkout Processing Rule	430
Barcoding Checkout Rule	431
Optional Message Presentation Rule	432
Variable Expense Codes Rule	432
Functions	434
Checkout All Planned Items	434
Reports	434
S_RPT020 - Issue Ticket Report	434

Stock Transfer Module 435

Business Rules	435
Alerts Rule	435
Bar Code Configuration Rule	436
Receiving Configuration Rule	436
Reports	437
S_RPT115 - Stock Transfer Report	437
Storeroom Stocking Module	438
Business Rules	438
Bar Code Configuration Rule	438

Reorder Review Module 439

Business Rules	439
Batch Stock Reorder Rule	439
Batch Processes	442
Stock Reorder - sdbp_stock_reoder.stock_reorder;	442
Functions	442
Reorder Wizard	442

Reports	442
S_RPT028 - About to Reorder Report	442
Receiving Module	443
Business Rules	443
Alerts Rule	443
Bar Code Configuration Rule	444
Default Directories Rule	444
Enforce Receiver Rule	445
Receiving Configuration Rule	445
Specification Upload Defaults	446
Web Configuration Rule	447
Batch Processes	447
Check Received PO Item - sdbp_chk_issd_po_item;	447
Invoice Resolution - sdbp_invoice-resolution;	447
Cost Accruals - sdbp_cost_accruals.cost_accruals;	447
Code Tables	447
Code Table 81 - Loftware Labels (Length = 15)	447
Functions	448
Bar Code Print Labels	448
Receive More Than Ordered	448
Receive All Items As Ordered	448
Reports	448
S_RPT107 - Delivery Receiving Report	448
S_RPT047 - Receipt Delivery Worksheet Report	448
S_RPT025 - Receiving Report	448
S_RPT216 - Receiving Report	448
S_RPT037 - Receiving Worksheet Report	448
Multi-Step Receiving Module.....	449
Fields	449
Sequence No.: Delivery ID	449
User-Defined	449
Business Rules	449
Alerts Rule	449
Bar Code Configuration Rule	450
Barcode Label Printers Rule	451
Receiving Configuration Rule	451
Vendor Performance Attributes Rule (Shipment Attributes View)	452
Batch Processes	452
Check Received PO Item - sdbp_chk_issd_po_item;	452
Cost Accruals - sdbp_cost_accruals.cost_accruals;	452
Invoice Resolution - sdbp_invoice-resolution;	452
Vendor Performance - sdbp_vendor_performance;	453
Code Tables	453
Code Table 57: Container Types (Length = 10)	453
Code Table 81 - Loftware Labels (Length = 15)	453
Code Table 58: NCM Disposition Codes (Shipment Attributes View) (Length = 20)	453
Functions	453
Accept Quality Items	453
Bar Code Print Labels	453
MSR Force PO Complete	453
Not Vendor Caused	454
Receive More Than Ordered	454
Receive All Items As Ordered	454
Reports	454
S_RPT107 - Delivery Receiving Report	454
S_RPT047 - Receipt Delivery Worksheet Report	454
S_RPT025 - Receiving Report	454
S_RPT037 - Receiving Worksheet Report	454
S_RPT140 - Completed NCMs	454
S_RPT216 - Receiving Report	454
Material Disposition Module.....	455
Business Rules	455
Repairable Processing Rule	455

Code Tables	456
Code Table 59: Material Disposition Repair Types (Length = 10)	456
Functions	456
Repair Removed Part	456
Batch Processes	456
Storeroom Repair Costs - sdbp_storeroom_repair_costs;	456
Managing Advanced Materials	456
Set Up for Advanced Materials Processing Functionality	457
Repairable Processing Business Rule	457
Component Processing Business Rule	457
Physical Inventory Module	458
Business Rules	458
Bar Code Configuration Rule	458
Physical Inventory Rules Rule	458
Physical Inventory Tolerances Rule	459
Code Tables	459
Code Table 212: Item Class Codes (Length = 10)	459
Functions	460
Adjust Store for Recount	460
Reports	460
S_RPT038 - Physical Inventory Listing Report	460
S_RPT039 - Physical Inventory Variance Report	460
S_RPT104 - Physical Inventory Listing Report	460
S_RPT108 - Inspection/Discrepancy Physical Inventory Report	460
S_RPT109 - Property Inventory - Items Not Found Report	460
Shipping Memo Module	461
Fields	461
Sequence No.: Shipping Memo No.	461
Business Rules	461
Shipping Memo Options Rule	461
Copy Record	462
SHIPMEMO - COPY RECORD	462
Reports	462
S_RPT210 - Shipping Memo Report	462
Property Management Module	463
Fields	463
Sequence No.: Property ID	463
Code Tables	463
Code Table 53: Property Types (Length = 20)	463
Code Table 55: Property Classes (Length = 20)	463
Copy Record	463
PROPERTY - COPY RECORD	463
Reports	463
S_RPT110 - Property Inventory - Discrepancies Report	463
S_RPT111 - Property Inventory - Items to be Inventoried Report	463
S_RPT109 - Property Inventory Report - Items Not Found	463
Consumables Module	464
Code Tables	464
Code Table 31: Consumable Types (Length = 6)	464
Code Table 32: Consumables Source Codes (Length = 8)	464
7 Customer Subsystem	465
Customer Module	465
Fields	465
Sequence No.: Customer ID	465
Copy Record	465
CUSTOMER - COPY RECORD	465
Code Tables	465
Code Table 15: Country Codes	465

Code Table 73: Property Types (Address (Detail) View)	465
Service Request Module	467
Fields	467
Sequence No.: Service Request No.	467
Next Approver Field	467
Business Rules	467
Expense Codes Rule	467
Code Tables	468
Code Table 240: Service Request Types	468
Code Table 241: Problem Codes	468
Code Table 242: Deposit and Payment Types (Billing Information View)	468
Code Table 246: Disconnect Location	468
Code Table 1195 - CCB Expense	468
Code Table 1196 - CCB Install Remove Flag	468
Copy Record	468
SERVREQ - COPY RECORD	468
Functions	468
Associated Service Request	469
Create WO from Service Request	469
Batch Processes	469
Cost Service Request - sdbp_cost_service_request.cost_service_request_rollup	469
Charts	469
S_CHT140 - Customer Follow-Up Calls	469
Metrics	469
S_MTRC1 - Customer Follow-Up Calls Pending - sdbp_metric_cust_follow_calls	469
Reports	469
S_RPT138 - Service Request Report	469
8 Enterprise Subsystem	470
Asset Type Analysis Module	470
Company Module.....	470
Enterprise Asset Module	470
Code Table 75 - 77: Asset Mobile fields 1-3	470
Enterprise Catalog Module.....	470
Organization Module	471
Plant Module	471
Fields	471
Plant	471
Description	471
Company	471
Organization	471
Locale	471
Local Currency and Fiscal Calendar	471
Locale Phone Format	472
Include in Run All Batch?	472
Multi-Plant/ Single Plant Usage	472
Using Multiple Plants	472
When to Use Multiple Plants	472
Separating Data in Oracle Utilities Work and Asset Management	473
Single Plant - Multiple Departments	473
Additional Considerations	473
Business Rules	473
Asset Hierarchy	474
Data Availability	474

Configuration Guide

This guide provides details about configurable items for each module in the system.

System configuration can be completed in any order according to the needs of your organization. The system is configured by setting business rules, code tables, required fields and default values, sequence numbers, duplication, order by options, accounts, vendor codes, and custom fields menus and lists of values.

Note: Once business rules, account settings, and other configuration items have been set, they should be changed only after careful consideration and consultation with Oracle Utilities Work and Asset Management. Improper changes can disrupt how the system processes your organization's information.

Use the [Table of Contents](#) to see convenient lists of configuration items in each subsystem and module.

New Installations

This guide is generally organized by subsystem and module, however, the following shows a suggested configuration order for new installations:

- Create Users
- Create Responsibilities
- Define the accounting hierarchy
- Configure system-wide settings including batch job control
- Set approvals processing
- Determine the asset hierarchy
- Create stock codes and storeroom structure
- Set additional modules, business rules, and settings according to your business processes

Generated: June 30, 2011 11:05 am

Chapter 1

General System Setup

This chapter outlines the key items that must be configured upon initial system implementation. Decisions such as whether or not to use auditing, various installation parameters, very commonly used code tables and views, and other parameters should be configured up front before delving into other business processes.

In addition, implementation teams should consider the business rules, functions, and batch processes that may need to be configured in order to determine which objects and functionality users have access to on their home page.

Audit Log

Whenever any of the database tables are modified in any way (usually on insert, delete, or update) the system tracks the change in the Auditing Log.

1. For each table the user wishes to audit, the audit entry in `sa_installation_parameters` should be set to ON. All others should be set to OFF.
2. After any change, User should run the procedure `SDBP_ALTER_TRIGGERS_SAUT` from SQL-Plus. This reads the `sa_installation_parameters` entry, and turns on/off the appropriate trigger based on what it reads in `sa_installation_parameters`.

Batch Processes

Please refer to the batch processing guide for

Refresh Materialized View(s)

`sdbp_materialized_view(job_in, plant_in)`; - Refreshes all existing materialized views owned by the `schema_user` defined in the given job.

To refresh a specified materialized view:

Modify (JOB_IN, PLANT_IN, MAT_VIEW_NAME_IN, REFRESH_TYPE) - Where:

- a. JOB_IN - Job number generated in Job Manager.
- b. PLANT_IN - Default plant.
- c. MAT_VIEW_NAME_IN - Materialized view to be refreshed (e.g. `SOLAP_ACT_COST_PLAN_EST`).
- d. REFRESH_TYPE_IN - Type of refresh to be done (F - Fast, C - Complete, A - Always perform complete, ? - Use default).

Example:

```
sdbp_materialized_view.refresh_materialized_view(966,'01','SOLAP_PLANNING  
_ACCURACY_IDX','C');
```

More information

Whenever an ordinary view's table is queried or updated, the DBMS converts these into queries or updates against the underlying base tables. A materialized view takes a different approach in which the query result is cached as a concrete table that may be updated from the original base tables from time to time. This enables much more efficient access, at the cost of some data being potentially out-of-date. If you, for some reason, need to have a materialized view refreshed at a different time than the regular schedule, you can modify the batch process to do so.

Business Rules

Asset Navigator Rule

The screenshot shows a configuration window titled "Business Rule ASSET NAVIGATOR". It includes fields for Rule ID (ASSET NAVIGATOR), Desc (Settings for Asset Navigator Functionality.), and Comment. Below these is a table with columns "Setting" and "Value". The first row is highlighted and shows "TOP LEVEL" and "ASSET". There is also a Description field at the bottom.

Setting	Value
TOP LEVEL	ASSET

This rule allows you to define whether the top level of the asset navigator hierarchy is ASSET (default) or DEPARTMENT.

Setting and Value

TOP LEVEL - Select either ASSET (default) or DEPARTMENT.

Copy/Paste Object IDs Rule

The screenshot shows a configuration window titled "Business Rule COPY/PASTE OBJECT IDS". It includes fields for Rule ID (COPY/PASTE OBJECT IDS), Desc (This rule is used to allow the ability to copy and paste object IDs from one module to another.), and Comment. Below these is a table with columns "Rule" and "Option". The first row shows "COPY/PASTE OBJECT IDS" and "YES". There is also a Description field at the bottom.

Rule	Option
COPY/PASTE OBJECT IDS	YES

Set the Option value to YES or NO depending on whether you want to allow or disallow copying of object IDs from one module to another.

Default Directories Rule

The screenshot shows a configuration window titled "Business Rule DEFAULT DIRECTORIES". At the top, there is a "Rule ID" field containing "DEFAULT DIRECTORIES", a "Business" dropdown menu, a "Parameter" dropdown menu, and a "Limit?" checkbox. Below this are "Desc" and "Comment" text areas. The "Desc" field contains "This rule defines default directories" and the "Comment" field contains "This rule is used when performing client-side operations". A table with two columns, "Directory" and "Path", is displayed. The "Directory" column lists: "BAR CODE LABEL DROP DIRECTORY", "INSTALLED DIRECTORY", "OPER DATA EXPORT DIRECTORY", "OPER DATA IMPORT DIRECTORY", "RFQ EXPORT DIRECTORY", and "RFQ IMPORT DIRECTORY". The "Path" column shows corresponding paths: "c:\of", "c:\sy", "c:\ter", "c:\ter", "c:\ter", and "c:\ter". Below the table is a "Description" text area containing "This is the default directory to put barcode label files into".

The Default Directories rule defines default locations for files outside of the Oracle Utilities Work and Asset Management database and is used for saving or calling files from the client computer. Individual users can establish settings in their individual User Profile record in the Administration subsystem that will supersede these business rule settings.

The Default Directories rule should not be confused with the similar Default File Locations rule, which is used to define specific file names and the paths leading to them.

Directory

BAR CODE LABEL DROP DIRECTORY - default directory to put bar code label files into.

INSTALLED DIRECTORY - directory where the application files are located.

OPER DATA EXPORT DIRECTORY - default directory for exporting Operational Data files.

OPER DATA IMPORT DIRECTORY - default directory for importing Operational Data files.

RFQ EXPORT DIRECTORY - default directory for exporting RFQ files.

RFQ IMPORT DIRECTORY - default directory for importing RFQ files.\

COMPONENT UPLOAD DIRECTORY - directory where files are stored when they are uploaded to support receiving multiple trackable components.

Path

This is the hard drive storage location for the corresponding file.

Default File Locations Rule

The screenshot shows a window titled "Business Rule DEFAULT FILE LOCATIONS". At the top, there is a "Rule ID" field containing "DEFAULT FILE LOCATIONS", a "Business" dropdown menu, a "Parameter" dropdown menu, and a "Limit?" checkbox. Below this is a "Desc" field with the text "This rule defines default file locations for Operating System files used by the Synergen Series". A "Comment" field contains two lines of text: "C:\Program Files\Microsoft Office\Office\WINPROJ.EXE" and "D:\microsoft office\Office\WINPROJ.EXE".

The main area is a table with two columns: "File" and "Pe". The "File" column lists several entries: MS PROJECT, MS WORD, MS WORDX, PERMIT ASP FILES, PRIMAVERA, PRINT MACRO, and PRINT TEMPLATE. The "Pe" column is empty. To the right of the table is a vertical list of drive letters: C:, C:, C:, C:, C:, C:, D:, D:, D:, D:, D:, D:, E:, E:, E:, E:, E:, E:, F:, F:, F:, F:, F:, F:, G:, G:, G:, G, H:, H:, H:, H, I:, I:, I:, I, J:, J:, J:, J, K:, K:, K:, K, L:, L:, L:, L, M:, M:, M:, M, N:, N:, N:, N, O:, O:, O:, O, P:, P:, P:, P, Q:, Q:, Q:, Q, R:, R:, R:, R, S:, S:, S:, S, T:, T:, T:, T, U:, U:, U:, U, V:, V:, V:, V, W:, W:, W:, W, X:, X:, X:, X, Y:, Y:, Y:, Y, Z:, Z:, Z:, Z.

At the bottom of the window is a "Description" field.

Define default file names and their locations for files outside of the Oracle Utilities Work and Asset Management database. The locations entered are used for saving or calling files from the client computer. Individual users can establish settings in their User Profile record in the Administration subsystem. User Profile settings supersede these business rule settings.

The Default File Locations rule should not be confused with the similar Default Directories business rule, which is used for defining paths leading to files with variable names.

File

List the default file names for operating system files used by Oracle Utilities Work and Asset Management.

MS PROJECT - This is the default file location where MS Project files will be stored.

MS WORD - This is the default file location where MS Word files will be stored.

PERMIT ASP FILES - This is the DNS or IP Address of the Webserver/Virtual Directory where ASP files, which are used in the printing of Blob attachments from the Permits module, are located. The path should be in the following format: Webserver/Virtual Directory.

PRIMAVERA - This is the default file location where Primavera files will be stored.

PRINT MACRO - Microsoft Word attachment-printing macro program path/filename.

PRINT TEMPLATE - Microsoft Word attachment-printing template path/filename.

Path

Enter the path and name for the corresponding file in this field. The maximum number of characters allowed for the path is 500.

Do Approvals Query

The screenshot shows the configuration window for the Business Rule "DO APPROVALS QUERY". The window title is "Business Rule DO APPROVALS QUERY". It contains the following fields:

- Rule ID:** DO APPROVALS QUERY
- Business:** Business
- Parameter:** Parameter
- Limit?:**
- Desc:** This rule uses "DO APPROVALS QUERY" processing to check for Approvals (detail) records.
- Comment:** The Approval Log item in the Views menu takes you to the Approval detail of the record you are on. The menu item for a record with Approval comments will show an asterisk "*" to the right of the word
- Option Table:**

Option	Option Status
APPROVALS	ON
- Description:** Enter ON into the "OPTION STATUS" column to force the system to automatically look for Approval comment per header record (causing a slight increase in system overhead when you execute a query) and sets the Approval

If the Option Status is set to ON the system checks for approval comments on records. If a record has attachments the system displays an asterisk next to the approvals link on the Views list in the module.

Do Attachments Query

The screenshot shows the configuration window for the Business Rule "DO ATTACHMENTS QUERY". The window title is "Business Rule DO ATTACHMENTS QUERY". It contains the following fields:

- Rule ID:** DO ATTACHMENTS QUERY
- Business:** Business
- Parameter:** Parameter
- Limit?:**
- Desc:** This rule uses "ATTACHMENTS" processing to check for Attachments (detail) records.
- Comment:** The Go To Attachments icon takes you to the Attachments detail of the record you are on. The icon for a record with Attachments attached is different than the icon for a record with no Attachments attached.
- Option Table:**

Option	Option Status
ATTACHMENTS	ON
- Description:**

If the Option Status is set to ON the system checks for attachments on records. If a record has attachments the system displays an asterisk next to the attachments link on the Views list in the module.

Do Notes Query

The screenshot shows the configuration window for the Business Rule "DO NOTES QUERY". The window title is "Business Rule DO NOTES QUERY". It contains the following fields:

- Rule ID:** DO NOTES QUERY
- Business:** Business
- Parameter:** Parameter
- Limit?:**
- Desc:** This rule uses "DO NOTES QUERY" processing to check for Notes (detail) records.
- Comment:** The Go To Notes item in the Views menu takes you to the Notes detail of the record you are on. The menu item for a record with Notes
- Option Table:**

Option	Option Status
DO NOTES QUERY	ON
- Description:** Enter ON into the "OPTION STATUS" column to force the system to automatically look for Notes per header record (causing a slight increase

If the Option Status is set to ON the system checks for notes on records. If a record has attachments the system displays an asterisk next to the notes link on the Views list in the module.

Drill-down Configuration Rule

The screenshot shows a web-based configuration form titled "Business Rule DRILLDOWN CONFIGURATION". At the top, there is a "Rule ID" field containing "DRILLDOWN CONFIGURATION", followed by two dropdown menus labeled "Configuration" and "Parameter", and a "Limit?" checkbox. Below these are three text input fields: "Desc" (containing "This rule is used to govern the behavior of drilldowns."), "Comment", and "Description" (containing "This rule is used to allow/disallow use of the Asset Navigator upon drilldown on an empty field."). The main part of the form is a table with two columns: "Rule" and "Option". The first row is expanded to show "USE ASSET NAVIGATOR" under the "Rule" column and "YES" under the "Option" column. Below the table is another "Description" field.

Rule	Option
USE ASSET NAVIGATOR	YES

Enable or disable the use of the Asset Navigator when performing drill-down from an Asset ID field in the application.

Set the USE ASSET NAVIGATOR rule key to YES if you want the system to open the Asset Navigator when you double-click on an Asset field. If this rule key is set to NO (default) the system opens the Asset module when you double-click on an empty Asset field.

Home Page Component Alias

Set a customized title for the Links component on the Home Page.

The screenshot shows a web-based configuration form titled "Business Rule HOME PAGE COMPONENT ALIAS". At the top, there is a "Rule ID" field containing "HOME PAGE COMPONENT ALIAS", followed by two dropdown menus labeled "Configuration" and "Parameter", and a "Limit?" checkbox. Below these are three text input fields: "Desc" (containing "This rule allows the override of the title for the Links Home Page component."), "Comment", and "Description". The main part of the form is a table with two columns: "Actual Name" and "Name". The first row is expanded to show "LINKS" under the "Actual Name" column and an empty field under the "Name" column. Below the table is another "Description" field.

Actual Name	Name
LINKS	

Actual Name indicates the default appearance for the Links. Enter text in the Name field to change this to customized text. You must log out and back in to see the result of this change on the Home page.

MDI Window Title Rule

Business Rule MDI WINDOW TITLE

Rule ID: MDI_WINDOW_TITLE Business Parameter Limit?

Desc: This business rule controls the title of the Multiple Document Interface Window of Synergen series Applications.

Comment:

Option	Display	Order	Prefix	Su
SHOW DATABASE CONNECT STRING	NO	5		
SHOW DEFAULT NAME	NO	4		
SHOW PLANT CODE	YES	2		
SHOW PLANT DESCRIPTION	YES	3		
SHOW USERNAME	YES	1		

Description: This rule determines if the database connect string is displayed on the MDI window title and the position of the connect string on the title.

Control the title of the Multiple Document Interface window. This rule determines whether or not the database connect string is displayed on the MDI window title and the position of the connect string on the title.

Option, Display, Order, Prefix, and Suffix

Enter YES or NO for each option in the Display column for each Option. Enter a sequence number for each option in the Order column to indicate the order in which each option should appear. You can also enter a Prefix or Suffix in the corresponding column for each option.

SHOW DATABASE CONNECT STRING - Determine whether the database name is displayed on the MDI window title and the position of the connect string on the title.

SHOW DEFAULT NAME - Determine whether the user's default name is displayed on the MDI window title and the position of the default name on the title.

SHOW PLANT CODE - Determine whether the Plant Code is displayed on the MDI window title and the position of Plant Code on the title.

SHOW PLANT DESCRIPTION - Determine whether the Plant Description is displayed on the MDI window title and the position of the Plant Description on the title.

SHOW USERNAME - Determine whether the Oracle Username is displayed on the MDI window title and the position of the Username on the title.

E-Mail Configuration Rule

Key Name	E-mail Mode
DEFAULT SENDER	
EMAIL INTEGRATION	ENHANCED
PO EMAIL DELIVERY RECEIPT	YES
PO EMAIL FILE LOCATION	

Define information specific to how the system processes e-mail, including the type of technology to use. You may need to enlarge the window or scroll to the right to see the Settings column.

Key Name and E-mail Mode

BC EMAIL DELIVERY RECEIPT - This key determines whether a delivery receipt should be sent to the user when he or she e-mails a blanket contract to a vendor.

BC EMAIL FILE LOCATION - Enter the location where the blanket contract e-mail file will be created in the Setting column.

DEFAULT SENDER - Enter a valid e-mail address to be used as the return address on system-generated e-mails such as alerts and error notifications. It is very important that default sender address be one that system administrators will receive, in case users need to respond to a system message.

The Default Sender address is also used on any e-mail where the sender does not have an e-mail address in his or her User Profile.

E-MAIL INTEGRATION - This key was previously used to choose the type of e-mail integration to be used in the system. The only current settings are ENHANCED or NONE. When the rule is set to NONE, users will only receive messages in their Oracle Utilities Work and Asset Management Inbox.

PO E-MAIL DELIVERY RECEIPT - Currently Delivery Receipt only works for messages delivered within the system. If the recipient receives a message in e-mail that was delivered from within the system, you will not receive a confirmation message when the message is opened.

PO E-MAIL FILE LOCATION - It defines the file location where the PO e-mail file will be generated. Enter the location where the PO e-mail file will be created in the Setting column.

You must also allow network access to the directory defined under the REPORTS OUTPUT PHYS DIRECTORY rule key in the Web Configuration Business Rule. Once this access is allowed, identify this network share in this rule key.

NOTE: SIA's e-mail integration uses SMTP relaying to send e-mail messages. If your e-mail server restricts these relay requests, then emails sent to people who do not have an

account on the e-mail server may not go through. The e-mail administrator must turn on SMTP relaying for the SIA Application server. This is usually done by specifying the IP address of the requesting server (SIA Application server) to the E-mail server.

Optional Message Presentation Rule

Business Rule OPTIONAL MESSAGE PRESENTATION

Rule ID: **OPTIONAL MESSAGE PRESENTATION** Configuration: Configuration Parameter: Parameter Limit?

Desc: This rule dictates where specific messages should be sent: to the bottom of the current window or to an Alert.

Comment: This processing applies to only certain types of messages; all other messages are directed by pre-determined processing.

Message	Type
CHECK PRIVS	ON
ERROR MESSAGES	ALERT
EXIT MODIFIED RECORD	ALERT
REQUIRED FIELD COLOR	DEFAULT
STOCK CHECKOUT WARNING	ON

Description

ON: Table-level privilege check is made by Synergen Series as soon as the user begins to insert a record.
 OFF: Table-level privilege checks are made by Oracle at the time the record is saved.

There are many events and functions that generate messages sent to the user. With the Optional Message Presentation Rule you can dictate where certain message types should be sent: to the bottom of the current window or to an Alert window opened on top of the current window. Note that this processing applies to only certain types of messages (listed in the “MESSAGE” column); all other messages are directed by pre-determined processing.

Also controlled through this Rule is table-level privilege checking performed by system processing. Standard Oracle database processing performs table-level privilege checks only when a user attempts to execute a function. That is, a user wants to insert a new record, fills out all of the information on the form, then attempts to save. At that point, Oracle checks to see if that user has insert ability on the table. If not, the user is given an error message and cannot save his work.

Privilege check processing reviews user privileges at the earliest possible time and then issues a message to the user indicating that they do not have the required privilege. In the same example, when the user presses the insert button, the system checks privileges and then issues a message if the user does not have the privilege. This processing involves a bit more overhead than simply letting Oracle check privileges at the time of execution but is far more user-friendly.

This Rule also defines the coloring of required fields.

Message and Type

CHECK PRIVS - If the Type field is set to ON for this rule key the system verifies a user’s table-level privilege as soon as he or she begins to insert a record. If this rule key is set to OFF all table-level privilege checks are made by Oracle at the time the record is saved.

ERROR MESSAGES - Set this rule key to MESSAGE in the to have an oracle error message displayed at the bottom of the window. Set it to ALERT to show a pop up box with the Oracle Error Message. Users can configure their user profile to set individual preferences for this option.

EXIT MODIFIED RECORD - Set this rule key to MESSAGE in the Type field to have this type of message displayed at the bottom of the window. Set it to ALERT to show a pop up box with the message. This applies to the warning message that a user sees when he or she attempts to leave a modified record without saving or undoing the change.

REQUIRED FIELD COLOR - Set this rule key to indicate the color that the system highlights required fields. Options are DEFAULT or 16 COLOR. Required field color can be changed for individuals in the User Profile module. The 16 COLOR setting should be used if users have problems with required fields not showing up with colored backgrounds. DEFAULT is entered in this column for those users running PC's with 256 colors (or greater).

Users can configure their user profile to set individual preferences for this option.

STOCK CHECKOUT WARNING - Enter ON in the Type column for the system to display a message that the issue quantity on the work order checkout request is greater than the estimated quantity on the Work Order Task Material Requirements. This message does not prevent the checkout; it is merely a warning. Enter OFF to prevent the message.

PIN Processing Administration Rule

Business Rule PIN PROCESSING ADMINISTRATION

Rule ID: PIN PROCESSING ADMINISTRATION Configuration Parameter Limit?

Desc: This rule utilizes the data stored in the User Profile to notify users upon logon that the current pin has expired and prompts the user for a new pin.

Comment: Use to turn "ON" or "OFF" pin processing and expiration checks upon logon.

Rule Enforcement	Option Status
ALPHA AND NUMERIC	ON
CHECK EXPIRATION	ON
LOCKOUT PIN	ON
MINIMUM PIN LENGTH	4
PIN DURATION	120
PIN PROCESSING	ON
PIN REUSE CACHE	1
RETRIES ALLOWED	5
USE PIN - CHANGE ORDER	ON
USE PIN - CHANGE REQUEST	ON
USE PIN - DIRECT CHARGES	ON
USE PIN - INVOICE	ON
USE PIN - PERMIT	ON

Description: Check for PIN during approval process of Direct Charges.

The PIN Processing Administration Rule manages PIN functionality throughout the system including using data stored in the User Profile module to notify approvers at logon if their personal identification number has expired.

ALPHA AND NUMERIC - When this parameter is set to ON, personal identification numbers must contain both alpha and numeric characters.

CHECK EXPIRATION - Set this rule key to ON to invoke PIN expiration checking. When an approver logs onto the system, the system checks their PIN against the expiration date stored in the User Profile module.

If the Option Status column is set to OFF, the system will not check the expiration date and will not prompt for a new PIN once the current PIN expires.

LOCKOUT PIN - If this option is set ON, the system disables a PIN after the number of failed attempts to enter the PIN specified in the Retries Allowed parameter. Once a PIN is locked, Administrative intervention is required to activate.

MINIMUM PIN LENGTH - The minimum number of characters required for all personal identification numbers.

PIN DURATION - The number of days personal identification numbers can be used by approvers before they expire.

PIN REUSE CACHE - This parameter stipulates the size of the cache of PINs to maintain to ensure a PIN is not reused. If set to five, for example, a user cannot enter a new PIN that is the same as any of the user's five previous PINs.

RETRIES ALLOWED - This parameter specifies the number of incorrect attempts a user is allowed before their PIN is disabled.

Use PIN - [Module] - Set this value to ON to have the system check for PIN during the approval process for the specified module.

Primary Menu Rule

Rule	Key 1	Key 2
CUSTOM MENU	in_house	In house

Determine whether or not users can interface their own Developer/2000 based applications by adding a custom menu called directly from the primary menu. This rule is checked only when the application starts up. The menu option will appear as the first option of the Admin menu in the Primary Menu.

Rule, Key 1, & Key 2

CUSTOM MENU is the menu which contains a sample PL/SQL menu set up to call your own form. Key 1 is the form name of the menu (without the file extension .mmb). An example would be MY_MENU. Key 2 is the label that will appear in the application.

Restrict List of Values Rule

The screenshot shows a configuration window titled "Business Rule RESTRICT LIST OF VALUES". It contains the following fields and controls:

- Rule ID:** RESTRICT LIST OF VALUES
- Configuration:** Configuration (dropdown)
- List:** List (dropdown)
- Limit?:**
- Desc:** This rule requires users to enter data in a field to narrow, or restrict, the List of Values (LOV's) help search before the database is queried. This processing is intended for those columns (prime keys) which
- Comment:** Enter in the "COLUMN NAME" column the field name (COLUMN_NAME) which will require input before the database is queried. For example, it is recommended that this Rule be used to restrict LOV's on
- Column Name:** A table with one column and five rows. The first row contains "PRIMARY_VENDOR_CODE".
- Description:** A text area for additional details.

Determine whether or not users are required to enter partial data into the fields listed here to narrow or restrict the list of values for these fields.

This processing is intended regulate searches on columns that will return a very large a number of records and cause a considerable system delay if all records were to be retrieved at once.

Column Name

Enter the field name for the field that will require input before the database is queried. For example, it is recommended that this Rule be used to restrict Lists of Values on STOCK_CODE, ASSET_ID and VENDOR_CODE. This Rule is not recommended to be used to restrict Lists of Values on code table driven fields.

Warning: There is a limit to the number of fields for which Restricted List of Value Processing can be implemented. If too many fields are listed, the later fields will be ignored. The limit to the number of fields is based upon the length of the global variable (255 characters in length) into which the field names are appended. Therefore, the total number of characters (including spaces between field names) cannot exceed the 255-character limit.

UDFs - Auto Copy Across Modules Rule

Business Rule UDFs- AUTO COPY ACROSS MODULES

Rule ID: UDFS- AUTO COPY ACROSS MODULES Business Parameter Limit?

Desc: This rule allows the user to copy the UDF values from one module to another based on the KEY VALUES

Comment:

From Module To Module	ON/OFF
BLANKET TO PO	ON
BLANKET TO REQUISITION	ON
BLANKET TO RFQ	ON
PM ROUTE PLAN TO SCHED ROUTE	ON
PO TO INVOICE	ON
PO TO RFQ	ON
REQUISITION TO PO	ON
REQUISITION TO RFQ	ON
RFQ TO BLANKET	ON
RFQ TO PO	ON
RFQ TO RFQ	ON
WORKORDER TASK MATERIAL TO REQ	ON

Description: Copy all the UDF values from Blanket Contract to PO

Define settings so that users can copy UDF values from one module to another. Select the Module to Module combination and enter ON or OFF depending on whether or not you want to allow users to copy all of the UDF values from the first module to the second module indicated.

Copying User-Defined Field Information between Modules

For many modules, information from all user-defined fields on one window can be copied to all the corresponding user-defined fields in a different module.

Module combinations include:

- Benchmark Work Order to Work Order
- Blanket Contract to Purchase Order
- Blanket Contract to Request for Quotes
- Fleet Benchmark Work Order to Fleet Work Order
- Purchase Order to Invoice
- Purchase Order to Request for Quotes
- Request for Quotes to Blanket Contract
- Request for Quotes to Purchase Order
- Requisition to Purchase Order
- Requisition to Request for Quotes
- Work Order Task Materials to Requisition
- Work Design Permits to Work Order Task Permits

The copied information goes from one Attribute column in the first table to the corresponding Attribute column in the second table, so you must make sure that the sending and receiving columns correspond (e.g. Attribute1 on table one and Attribute1 on table two). The user-defined field labels do not have an impact on this processing.

For example, if you create a user-defined field labeled 'X' on the Requisition table using the Attribute1 column, and a second user-defined field labeled 'X' on the Purchase Order table using the Attribute2 column, the information will not copy over to 'X' on the Purchase Order. Instead, it will copy to the Attribute1 column of the Purchase Order table – which may not have an associated user-defined field at all.

How to Copy User-Defined Fields Information Between Modules

1. Open the UDFS - Auto Copy Across Modules Business Rule
2. Find the appropriate From Module to Module option.
3. Set the associated ON/Off field to ON.
4. Click Save.

Unit of Measurement Rule

UOM	Value
UNIT OF MEASUREMENT	ENGLISH

This rule allows users to set whether to use the English or Metric system in labels on reports S_RPT075, S_RPT076, S_RPT077. Setting the rule key to METRIC causes the system to display kilometers and KPL and setting it to ENGLISH causes the system to display miles and MPG.

Code Tables

The following code tables include values that are used for fields in that are used in several modules and views throughout the system. They should be configured to reflect your business practices.

Code Table 54: Note Types

Note Type field - Most of the modules, and many of the detail windows, in the system have a Notes view that allows you to enter and maintain notes or comments about the record. Enter valid note types for your organization in Code Table 54. For example, you may want to include a Buyer type to apply for purchasing records, or a Safety type to apply to work orders.

All Notes views look alike, function in the same way, and include the same types from Code Table 54 throughout the system. When a record has an associated note the word Notes on the Views list will have an asterisk next to it.

Code Table 186: Manufacturers

Manufacturer field - Most modules in the system include a Manufacturer Data view where you can indicate the Manufacturer and part number's associated to the record. Use Code

Table 186 to define any manufacturers that might be associated with any of your organization's assets, stock items, included on bills of materials, or otherwise used.

Event Queue

The system manages a queue of requests, such as emails or charts, which need to be processed in the Event Queue module.

Clearing Events

Select Clear Events at the bottom of the screen to purge the completed and failed events from the queue. The system will not delete events that are still pending.

Processing Retries

Within the config.properties file, the "queue_retries" property defines the number of times an event request that has errored during processing will be reattempted. Events in "retry" status will be processed when the server is restarted or when a Job Manager job has been scheduled to perform this action.

Set a Batch Job to Process Retries

Open the Job Manager module and create a new batch job with the following command entered in the Procedure field:

```
declare
response varchar2(2000);
begin
response
:=utl_http.request('process_queue_url?type=retry')
end;
```

The **process_queue_url** is the URL found in the process_queue_url column of the SA_INTERNET_INTEGRATION record that applies to the Oracle Utilities Work and Asset Management server.

Example:

```
utl_http.request('http://spl-london.us.oracle.com:7779/DV19X/synergen/EventServlet?type=retry')
```

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

DISABLE CUSTOM SQL

This function excludes users from being able to use Custom SQL on search screens throughout the system. The best way to assign this function is by adding the users to a special Responsibility called "Disable Custom SQL" instead of adding the function to a regular responsibility profile.

1. **Open the Responsibility module.**
2. **Search for the Responsibility named "DISABLE CUSTOM SQL".**

This special responsibility was delivered with the release and is designed to only include the function needed to disable Custom SQL.

3. **Select the Assigned Users view.**

4. Add the user to the list.

Entity Relationship Viewer

Controls access to the Entity Relationship Viewer accessed from the home page Actions list.

ESRI3 Viewer

Grants the ability to use the ESRI3 Viewer as the GIS viewer, and enables access to the ESRI3 Viewer action access from the home page Actions list.

GIS Viewer

Grants the ability to use the Oracle GIS Viewer as the GIS viewer and enables access to the GIS Viewer accessed from the home page Actions list.

Graph Viewer

Controls access to the Graph Viewer accessed from the home page Actions list.

Issue Uncompiled Objects Msg

Determines which users see the uncompiled object message on the main module.

News Administration

Defines which users are authorized to administer home page News Links.

Reorder Wizard

Allows users to have access to the Reorder Wizard from the home page Actions list.

Installation Parameters

The installation program for new installs and upgrades prompts the administrator to choose settings for these parameters, however, if it becomes necessary to modify these parameters, you can make changes in the Installation Parameters module.

AUDIT LOG- Objects beginning with SAUT

ON/OFF

These objects control whether or not the indicated module is tracked in the system audit log module. The value controls whether the trigger is enabled or disabled.

ENABLE PASSWORD RESET

When set to ON the “Forgot Password” link is present on the login screen and users can click this link to have a temporary password e-mailed to the e-mail address in their user profile. Please refer to the [password reset](#) topic in the Installation Parameters chapter for more information.

PHONE_NUMBER_FORMAT

Ex. (XXX) XXX-XXXX

This is the phone number format used by the SIA application. Example: a raw value of 9259357670 with a format mask of XXX-XXX-XXXX would result in a displayable phone number of 925-935-7670.

For non-english installations, the code should be set to NO FORMAT.

SPELL CHECK

ON/OFF

This option controls the Spell Checking feature.

Transaction Logs - Objects beginning with SDBT

ON/OFF

Most of them trigger a transaction to populate a log, although some trigger other events. The value controls whether the trigger is enabled or disabled.

WORKFLOW MESSAGE DIALOG

ON/OFF

Set this option to ON to resolve mouse focus issues that can result from initiating a workflow. If it is set to ON, a confirmation dialog is displayed after the user initiates a workflow such as opening a saved search, bookmark or alert. If it is set to OFF, no dialog is displayed, but the user may experience mouse focus issues once the workflow results are displayed.

Database, Install and System Administration

The following sections include database administration information that may help to improve system functionality

E-Mail Integration

In 11g databases, there is additional security that is configured by default to be turned ON. This security does not allow access out of the database without a script being run to enable this access.

Run the following line at an sqlplus prompt to verify whether the security access is stopping email integration from working:

```
select utl_http.request('http://www.proligence.com') from dual;
```

If this sql fails (example below) the security is still turned ON:

```
ERROR at line 1:
ORA-29273: HTTP request failed
ORA-06512: at "SYS.UTL_HTTP", line 1577
ORA-12535: TNS:operation timed out
ORA-06512: at line 1
```

Run the script, 7426686.sql (included in the 1.8.0.2 patch), to configure the 11g database to allow external network services to be accessed by the Oracle Utilities Work and Asset Management application similar to the default security privilege in the 10g or 9i database.

Note: The script will only work in an Oracle 11g database.

Enhanced Security

The 11g database can be installed with enhanced security, but this option should not be installed. The Oracle Utilities Work and Asset Management application does not support the mixed case/lower case characters required for enhanced security.

If enhanced security was installed, you will need to manually turn off case sensitive support for passwords:

Disable Case Sensitive Support for Passwords

1. **cmd> sqlplus synergen/pwd@wamprod.**

```
SQL> SHOW PARAMETER SEC_CASE_SENSITIVE_LOGON
```

2. **Modify the value to FALSE.**

```
SQL> ALTER SYSTEM SET SEC_CASE_SENSITIVE_LOGON = FALSE;
```

3. **Modify SYNERGEN password as a mixed case.**

```
SQL> alter user SYNERGEN identified by Asdf; //mixed case, the new
password is 'Asdf'
```

Changing the Password

```
alter user synergen identified by password;
```

Checking the Settings

```
select profile, resource_name, limit from dba_profiles where resource_type='PASS-
WORD' order by profile;
```

Failed Logon Attempts

Use the `failed_logon_attempts` property to set the number of tries each user has before being locked out of the system. Please note, that for each logon attempt, system processing appears to log-on 2 or 3 times. Given this, if you want users to have 5 attempts, the failed logon attempts property should be set to at least 15 or higher to account for system processing which also log as attempts. Run the following to alter the database setting:

Set maximum number of retries to log in:

1. **cmd> sqlplus synergen/pwd@wamprod.**

```
SQL> SHOW PARAMETER FAILED_LOGIN_ATTEMPTS
```

2. **Set the maximum number of retries.**

```
SQL> alter profile default limit FAILED_LOGIN_ATTEMPTS 30;
```

Unlocking an Account:

You can unlock a user account through SQL using the following command:

```
alter user synergen account unlock;
```

This can also be accomplished in the User Profile module using the [Unlock User Database](#) action.

Managing Log Files

OAS includes data logging to track functioning of the system. By default, Oracle Utilities Work and Asset Management uses this logging to track errors and/or debugging information. Log files grow in size taking up system resources and cannot be changed or deleted unless the server instance is stopped. Follow the steps below to set the system so that the log files can be deleted without stopping the server. To do this you will specify a rolling log file of specific sizes so that the resulting log files are more manageable.

To enable the log file rotation:

1. **Stop the Oracle AS instance.**

If your Oracle AS version is 10.1.3.0.0 or higher, go directly to step 3. (Oracle AS 10.1.3.0.0 already has the log file rotation functionality, no patch is needed to be applied to this version.)

2. **Apply Patch 4489980 to the Oracle AS instance.**
3. **Modify the java-options of the target OC4J instance to add the following:**

```
-Dstdstream.filesize=2.5
```

```
-Dstdstream.filenumber=5
```

(the above setting will make the files rotate if they hit 2.5MB and will only keep 5 files - the oldest one gets deleted).

4. **Modify the OC4J-options of the target OC4J instance to add the following:**

```
-out $ORACLE_HOME\opmn\logs\std.out
```

-err \$ORACLE_HOME\opmn\logs\std.err

(where \$ORACLE_HOME is the directory for your AS installation.)

5. Start the Oracle AS instance.

(the log files will be created in

\$ORACLE_HOME\opmn\logs\

The java options and oc4j options mentioned above will end up in the opmn.xml file.

The following shows an example:

```
<process-type id="OC4J_DV19M" module-id="OC4J">
  <module-data>
    <category id="start-parameters">
      <data id="java-options" value="-server -Xrs
-
Djava.security.policy=D:\ORAAS102\j2ee\OC4J_DV19M\config\java2.pol
icy
-Djava.awt.headless=true -Dstdstream.filesize=2.5 -
Dstdstream.filenumber=5"/>
      <data id="oc4j-options" value="-out
D:\ORAAS102\opmn\logs\DV19M_std.out -err
D:\ORAAS102\opmn\logs\DV19M_std.err"/>
    </category>
    <category id="stop-parameters">
      <data id="java-options"
value="-
Djava.security.policy=D:\ORAAS102\j2ee\OC4J_DV19M\config\java2.pol
icy
-Djava.awt.headless=true"/>
    </category>
  </module-data>
  <start timeout="900" retry="2"/>
  <stop timeout="120"/>
  <restart timeout="720" retry="2"/>
  <port id="ajp" range="12501-12600"/>
  <port id="rmi" range="12401-12500"/>
  <port id="jms" range="12601-12700"/>
  <process-set id="default_island" numprocs="1"/>
</process-type>
```

Proxies

All operations against the database are performed with the permissions of the logged in user's database account. Any security restrictions placed on the database account will take effect.

The config.properties setting, db_proxy_session_helper_class, with a default value of "synergen.db.OracleAsDbProxySessionHelper" controls this security feature. This value must not be modified. If the configuration setting is not present, the system will continue to function normally, but there will be messages in the log files indicating the setting is missing.

Application Server Configuration

NLS Configuration

To solve an issue found in testing NLS support, JDBC drivers were updated from 10.2.0.1 and 10.2.0.4 in release 1.9. The NLS jar file was added to the classpath. These are the Java classes that SIA will use to access the database.

Specifying the drivers is not a default installation step, so the appropriate drivers should be downloaded after installation. This is definitely necessary if you need to complete NLS

configuration which requires these specific drivers otherwise you may encounter errors.

Modified files include:

.../synergen/WEB-INF/lib/ojdbc14.jar

.../synergen/WEB-INF/lib/orai18n.jar

formsweb.cfg

In the formsweb.cfg file make sure the "archive" setting points to the "frmwebutil.jar" instead of the "webutil10123.jar". This setting will pull the frmwebutil.jar file located in the \ora10gMID\forms\java

Before

```
archive=frmall.jar,../synergen/jars/webutil10123.jar,../synergen/jars/jacob.jar,../synergen/jars/jspell2n_java11.jar,../synergen/jars/syn.jar,../synergen/jars/synergenpjcs.jar
```

After

```
archive=frmall.jar,frmwebutil.jar,../synergen/jars/jacob.jar,../synergen/jars/jspell2n_java11.jar,../synergen/jars/syn.jar,../synergen/jars/synergenpjcs.jar
```

Security Certificate

To ensure that computers recognize the latest Oracle JAR security certificate, it may be necessary to clear the Java Plug-in cache and remove existing Trusted Certificates. The existing certificate will be identified as Oracle Corporation from VeriSign. This will force your system to read the new certificate and open the Java Plug-in Security Warning panel at the beginning of your next Forms session. You can then select the "Always trust content from this publisher." option on the Java Security Warning panel to use the new certificate in all future sessions.

To Clear the Java Plug-in Cache and Remove the Security Certificate

1. **Open the Windows Control Panel (start > settings > control panel).**
2. **Double click on the Java icon.**
3. **Select the "General" tab.**
4. **Click on the "Settings..." button.**
5. **Click the "Delete Files..." button.**
6. **Verify that the "Applications and Applets" option is selected.**
7. **Click the "OK" button.**
8. **Select the Security tab.**
9. **Click the "Certificates..." button.**
10. **If necessary, select the certificate issued to "Oracle Corporation", issued by "VeriSign" in the list of Trusted Certificates.**
11. **Click the Remove button.**
12. **Click the "OK" button.**
13. **Close the Windows Control Panel.**

Single Sign On

The application server can be configured to address the need to centralize authentication of different applications at a site. This "Single Sign-On" concept will allow users to logon

to one system, and be granted access to other systems. Oracle Utilities Work and Asset Management needs to be configured as an “external” application to manage the many parts of the user account that are based within the database.

Application Server Configuration

These configuration instructions apply to Oracle Application Server 10G Release 2.

1. Access the SSO Server Administration pages

`http://server:port/pls/orasso`

2. Logon to the SSO Server. You must be a member of the OID Group "cn=iASAdmins".

3. Click the "SSO Server Administration" link.

4. Click the "Administer External Applications" link.

5. Click the "Add External Application" link.

6. Add "Utilities Work and Asset Management" as an External Application by entering the following information. ("server" is the server hosting the Work and Asset Management SIA server and "port" is the listening http port.)

Under External Application Logon

a. Application Name: <the name of the application as you want it to appear on the link>

b. Login URL: `http://server:port/synergen/Home?tgt=Main`

c. User Name/ID Field Name: `username`

d. Password Field Name: `password`

Under Authentication Method

a. use the "POST".

The new external application link will now be available on the SSO screen.

Authentication Redirection

Some Oracle Utilities Work and Asset Management installations will require that the user be navigated to a non-Oracle Utilities Work and Asset Management page (instead of the logon page) after logging out.

An example for this is an installation that uses SSO for authentication before allowing access to Oracle Utilities Work and Asset Management.

The redirected page is specified in the `config.properties` file in the `"logoff_page_url"` setting. The default value is `"Logon?tgt=Main"`. You should use the full URL including the protocol. Example: `http://www.oracle.com/`. Other configuration settings include:

- **ssoMode:** true or false where true indicates that Oracle SSO should manage authentication. If true, authentication is assumed to be managed by the web server.
- **home_page_url:** the URL to navigate to after authentication
- **logon_page_url:** the URL to navigate to if authentication is required
- **logon_error_url:** the URL to navigate to if user attempts to navigate to a path where authentication is required, but the user has not logged in yet (and SSO is not enabled)

- **logoff_page_url:** the URL navigated to when the user logs out of the Oracle Utilities Work and Asset Management application. Normally, this is the Logon Main page.

Transaction Logs

The system records transaction information for many modules in Transaction Logs. Transaction Logs can provide a tracking tool that is useful in finding out when charges, status changes, or other changes to information in a particular module. You can also search for log entries for particular criteria such as changes made within a specified date range or by a specific user.

While Transaction Logs are not configurable, it is important that you know where to find this summary information for transactions that take place during your use of the system.

Transaction logs are display only. The information shown is drawn from the module indicated in the Help File topic Modules with Transaction Logs.

Available Transaction Logs

Account Log	Auditing Log	Blanket Contract Log
Checkout Request Log	Component Log	Crew Activity Log
Direct Charges Log	Document Control Log	Inspection Log (Asset)
Job Manager Log	Keys and Locks Log	Payroll Log
Property Log	Purchasing Log	Receiving Log
Runtime Entry Log	Service Contract Timesheet Log	Storeroom Transaction Log
Timekeeping Log	Work Order Activity Log	

Charts, Metrics, and Reports

In order for users to have access to charts, filtered metrics, or reports they must have the object added in their responsibility profile. Consider how much of this information needs to be accessed by the user as you are developing your responsibility matrix, and assign responsibilities accordingly.


Localization

The application includes functionality that allows your organization to specify localized currency, telephone formats, numbers and, to some extent, languages. Configuration of the Plant module, the Field Localization view of the Modules Administration Forms module, currency codes in the Currency Exchange Rates module and the Unit of Measurement business rule controls these localized settings. In addition to field localization, translation of code table code descriptions allows for system wide translation of values related to those codes.

Note: Be aware that while there are ways to alter the system to support different locales (currency code, phone number format, code table values, field labels), they system is only officially certified to support English in an English installation and Spanish in a spanish installation. Furthermore, locale settings should not be configured with the expectation that they can be turned on or off or used within segments of the application. These are “all or nothing” settings which will apply throughout the application once they are configured.

Field Localization View in Modules Administration Forms

The Field Localization view allows you to customize labels for the fields on a form.



'Field Localization view

Field Localization settings are dependant on the [Plant](#) where they were configured. For example, a user can view all localized fields for Plant 01, but if he or she logs on to Plant 02 where no customized field labels are set, only system labels will be available. This rule is true for most customized settings.

How to Configure Localized Fields

1. Open the Modules Administration Forms Module.
2. Select Field Localization from the Views list.
3. Select a block name in the upper right corner of the screen.
4. Select the field on that block from the list of values in the Field Name column.
The system returns the known System Label.
5. Enter a customized Label and Hint text, if desired.


The label and hint entered will overwrite the system label and hint the next time you open that form and block. If you enter a new label that is longer than the original label, the system displays a warning. However, there could still be enough space to display your label despite the warning. In this case you should view the actual module screen before deciding to modify the label that you have chosen.

6. Use the last column on the screen to designate a specific display format for the field, if needed.

You should consult with customer support before modifying any display formats since placing the wrong type of format on a field might have an adverse affect on your ability to input and store data elsewhere in the system.

Locale Fields in the Plant Module

Included in the Plant module are fields which allow you to determine your location and the phone format that should be used in that location. Localization settings can vary by Plant in one organization.



Plant module


Locale - The locale field allows you to set the plant location and local language used. These settings affect aspects of the system such as using postal codes rather than zip codes or whether the English or Metric system is used in measurements.

Locale Phone Format - The Locale Phone Format field allows you to set the appropriate formatting for phone number fields. Users enter digits into a phone number field on another record and the system automatically formats the number according to the format set here. This formatting also applies to where phone numbers appear on reports. Select NO FORMATTING to allow free form entry of numbers in any format.

If one phone format is chosen and data is entered, then the format is changed here, the system does not re-format existing data. Please use care and forethought in choosing a phone format. Most US clients will not want to adjust this field from the default.

Using Currency Codes for Localization

The [Currency Exchange Rates](#) module allows for the creation of multiple exchange rates per currency code. When the exchange rate is updated, the new effective date is stored and the previous rates and effective dates are kept as a log. This functionality provides an audit trail of prior exchange rates used for procurement.



Currency Codes module

Currency codes and exchange rates are entered on purchasing documents to calculate the appropriate procurement costs. To indicate which code should be defaulted on purchasing records, open the Plant module in the Enterprise subsystem and enter the default code in the Local Currency field. This code is displayed as the base currency in the upper right corner of the Currency module record.

Currency - Create unique currency codes as appropriate to your business needs.

Effective Date, Exchange Rate, and Comments - The table displays the rate from a foreign currency to your base currency and from your base currency to the foreign currency. Exchange Rates can be entered manually with comments as they change. When

you enter one exchange rate, the system provides the other rate. The system also defaults the current date for the Effective Date, but this can be changed if necessary.

Using Code Tables for Localization

In addition to setting values for currency codes, fields, and formatting in the Plant module, you can also translate the description for any code table code to show translated values throughout the system where those codes are referenced. For example, if you wanted to show translated values for code table 3, maintenance codes, you would change the values in the "description" column to translated values in the other language, overwriting the English. The lists of values for the fields referencing this code table would then show the translated description, while the code would remain the same.

Configuring Internationalized Numbers

In some countries, large numbers are represented differently than what is defined as the default in Oracle Utilities Work and Asset Management. For example, the number 1000000 (one million) is represented as 1,000,000 in the United States and as 10,00,000 in India.

If needed, you can alter the grouping of segments in long numbers by modifying the SA_LOCALE table. This table consists of a row entry for each locale. Each row consists of two columns:

- **NUMBER_GROUPING_SIZE_PATTERN** –represents how digits in a number are grouped together in that locale
- **NUMBER_GROUPING_SIZE_EXAMPLE** – an example number that follows the pattern]

Table 1: Representation of SA_LOCALE with explanation

Locale	NUMBER_GROUPING_SIZE_PATTERN	NUMBER_GROUPING_SIZE_EXAMPLE	Explanation of the pattern
United States	3	1,254,689	Three digits are always grouped together. This is the default behavior of WAM and most commonly used grouping worldwide.
India	2,3	12,54,689	Three digits to the left of the decimal point of a number are grouped together. Subsequently, only two digits are grouped together.

Number Grouping Convention

Do not use space, period or any separator other than a comma to denote the NUMBER_GROUPING_SIZE_PATTERN.

Separators

The comma used in the grouping pattern should not be confused with the separator that is used when displaying actual numbers. Since the Oracle Utilities Work and Asset Management is only certified for English and Spanish, it is not possible to alter the separator used to separate the actual numbers. I.e. it cannot be changed to a period or semicolon.

Batch Processing

This section describes general batch processes and business rules which affect overall system functionality.

A batch process is a task that the system runs automatically. Such tasks can include making updates, purging obsolete data, generating schedules, or performing other automatic functions established by your organization without user intervention. Batch processing uses computer resources efficiently and facilitates off-hour completion of time consuming tasks that can slow down the system.

Job Manager and Job Manager Log modules

Batch processes are stored as database packages and database procedures, and are managed from within the system through the Job Manager module. Each Job Manager record has a system-generated number that uniquely identifies the “job”, or scheduled database procedure. The batch job can call one or more procedures to run at the specified run-time interval.

The Job Manager Log lists a complete set of messages issued by procedures as they were run. Each run of a procedure is uniquely identified by the Job Sequence Number, allowing you to research Job Manager Logs for one or many Procedures, and each run of a Procedure.

Batch Processes

Job Manager - `sdbp_job_error_log ((job_in, plant_in, sysdate-365));`

Generates entries in the Job Manager Log.

Purge Data - `sdbp_purge_data;`

Purges (deletes) data from the system database tables as defined in the Batch Purge Parameters Business Rule. Currently Alerts and Batch Messages are reviewed, deleting only those records that are older than the number of days defined in the rule for that item.

Run All Batch - `sdbp_run_all_batch;`

Calls all of the batch procedures defined in the Batch Job Control business rule. `SDBP_RUN_ALL_BATCH` generally includes all procedures that need to run on a daily basis. Procedures that need to run at different periodic intervals, such as once a year or at the end of the Pay Period should be scheduled separately.

How to Create a New Batch Job

Use this action to set batch jobs to run on an individual schedule when you don't want to include them in Run All Batch.

1. **Open the Job Manager module.**
2. **Select Create Job from the Actions list on the Search Options screen.**

The Update Job Window opens.

3. **Enter Job information.**

In the description field, enter the database package or procedure name (as stored in the database), followed by the Job Number (NN) displayed in the upper left corner of the window and the Plant Code ('PC') that you want this Job to process, followed by a semi-colon.

Packages:PACKAGE . PROCEDURE_NAME (NN, 'PC');

Procedures:PROCEDURE_NAME (NN, 'PC');

You can then enter a time Interval for automatic cycling of the procedure and the Next Run Date (and time) that you want the procedure to begin cycling.

4. Click the Save icon when you have entered all necessary information.

Business Rules

Batch Job Control Rule

Business Rule BATCH JOB CONTROL

Rule ID: Business Parameter Limit?

Desc: This rule is used to include or exclude certain batch processes from the regular batch cycles. Specific batch processes which may be turned on or turned off are listed in the "BATCH PROCESS" column.

Comment:

Batch Process	Option Status	Job
010 COST STOCK	YES	sd
020 COST ACCRUALS	YES	sd
025 COST ADJUSTMENT	YES	sd
028 POST TIMESHEET	YES	sd
030 COST LABOR	YES	sd
033 DIRECT CHARGES	YES	sd
035 PAY VOUCHER	YES	sd
040 COST INVOICE	YES	sd
044 PROCESS SERVICE TIMESHEET	YES	sd
045 COST SERVICE INVOICE	YES	sd
048 ACCUMULATE POSTED	NO	sd
050 HELD FOR PARTS	YES	sd
060 FINISH W/O	YES	sd

Description: SDBP_COST_STOCK.COST_STOCK processes costs for stock transactions which have not yet been posted. Information is selected from the table SA_INVENTORY_LOG and posted throughout the system as required. Once a

Include or exclude certain batch processes from regular batch cycles.

Batch Process, Job, and Option Status

Specific batch processes that can be turned on or turned off are listed in the Batch Process column. All batch procedures listed and turned on will run as part of SDBP_RUN_ALL_BATCH in the order specified in the Batch Process column.

Enter YES in the Option Status column if you want the batch process to run regularly, and NO if you do not want it to run. The Job column identifies the stored database procedure associated to each batch process.

Note that the order in which batch procedures are run makes a difference since a batch procedure may be dependent upon the data processed in another batch procedure. If they are run out of order, you may not see the data (such as cost roll-ups) for the batch run until the next time batch procedures are run.

Please refer to the [Batch Process Descriptions](#) for specific information on each process.

Batch Purge Criteria Rule

Business Rule BATCH PURGE CRITERIA

Rule ID: BATCH PURGE CRITERIA Business Parameter Limit?

Desc: This rule defines criteria for batch purge processing.

Comment: Batch processing. Define rule keys to specify criteria for purging of data in batch jobs.

Batch Processing	Status 1	Status 2	Status 3	Status 4
▲ EVENT QUEUE STATUSES	FAILED	FAILED		
REQUISITION PO STATUSES	CLOSED	CANCELED		
▼ WORK REQUEST WO STATUSES	CLOSED	CANCELED	REJECTED	HISTORY
▼				

Description: Work requests associated to work orders in the statuses entered in the Status 1 - 4 columns are purged. For example, if the value in the Status 1 column is set to CLOSED, the system purges any work requests associated to work orders in CLOSED status.

Define the status values which determine when to delete obsolete data. Records are deleted when batch purge processing runs. Enter the applicable statuses in the Status 1, Status 2, and Status 3 columns for each record type. For example, for work requests, if the value in the Status 1 column is set to CLOSED, the system purges any work requests associated to work orders in CLOSED status.

Batch Processing

EVENT QUEUE STATUSES - Delete event queue entries that are in the statuses identified in the status columns.

REQUISITION PO STATUSES - Delete requisitions associated with purchase orders in the statuses identified in the status columns. Typically, Requisitions are considered unnecessary after the PO has been CLOSED or CANCELED.

WORK REQUEST WO STATUSES - Delete work requests associated to work orders that are in the statuses identified in the status columns. Recommended options for Status 1 - 4 include work orders in CLOSED, CANCELED, HISTORY, or REJECTED status. Although it is possible, it is NOT recommended that you purge work requests associated to work orders in PLANNING, PENDING APPROVAL, APPROVED, ACTIVE or FINISHED status.

STATUS 1, STATUS 2, STATUS 3 - These columns indicate the statuses for the records that are purged. Status 1 is the prime status to be deleted. Status 2 and 3 are other desired statuses.

Batch Purge Parameters Rule

Batch Parameters	Days
ALERTS	1
AUDIT LOG	0
BATCH_MESSAGES	7
EVENT QUEUE	5
REQUISITIONS	9
WORK REQUESTS	0

As system data ages, it often becomes of little or no value to users. Purging old data regularly prevents tables from growing too large and helps maintain a quick system response time when querying those tables.

The Batch Purge Parameters Rule defines, per specific type of data, the age of a record before batch processes purges it. Note that the specific routines called for purging are already defined, purging either a single record at a time or a header record and its associated view, whichever is appropriate.

Batch Parameters and Days

ALERTS - Set the number of days the system should retain Alerts on the home page. Purge processing compares the Alert Date to the current date minus the number of days listed in the DAYS column, and deletes any messages that fall outside of that range.

AUDIT LOG - Set the number of days the system should retain Audit Log entries. Purge processing compares the date that the entry was made to the current date minus the number of days listed in the DAYS column, and deletes any messages that fall outside of that range.

BATCH_MESSAGES - Messages generated by batch processing and are stored as records in the Job Manager module so that you can easily access and review them at any time. Purge processing compares the Batch Message Date to the current date minus the number of days listed in the DAYS column, and deletes any messages that fall outside of that range.

REQUISITIONS - Purge Processing compares the PO Status Date (for status settings in the Batch Purge Criteria business rule) to the current date. When the result is greater than the number of days listed in the DAYS column, the Requisition is deleted from the system.

WORK REQUESTS - Purge Processing compares the Work Order Status Date (for status settings in the Batch Purge Criteria business rule) to the current date. When the result is greater than the number of days listed in the DAYS column, the work request is deleted from the system.

Batch Process Descriptions

The following batch processes are configured in the Batch Job Control business rule, and can be set to run or not run when Run All Batch is triggered.

Account Distribution module	ACCOUNT DISTRIBUTION TEMPLATE - sdbp_defaults_accounts_status(job_in, plant_in);- You are able to set future start dates in the Account Templates module. This process runs today's start dates and sets those records to active on that day.
Service Timesheet Service Invoices	ACCUMULATE POSTED SERVICE TIMESHEETS - sdbp_process_service_timesheet.accumulate_posted(job_in, plant_in); - Generates Service Contract Invoice records and associated Invoice Line Items for each Service Contract Timesheet in posted status with the Auto Pay indicator checked.
Blanket Contract module	AUTO ACTIVATE BLANKETS - sdbp_blanket_services.auto_activate(job_in, plant_in); - Sets Blanket Contracts to Active status on the Initiation Date indicated on the Blanket Contracts.
Blanket contract module	AUTO CLOSE BLANKETS - sdbp_blanket_services.auto_close(job_in, plant_in); - Closes Active Blanket Contracts on the Expiration Date or the Extended Date indicated on the Blanket Contracts.
Employee module, Timekeeping module	AUTO CREATE TIMESHEETS - sdbp_auto_create_timesheet.main(job_in, plant_in); - Triggers functionality where the system automatically creates timesheet records for employees as designated on their Employee record. The system can be configured to automatically create timesheets for employees who work a fixed schedule by checking the Automatically Create Timesheet? Indicator in the Auto Timesheet Schedule view in the Employee module.
AMMO Only	CHECK LOT EXPIRATION - sdbp_check_lot_expiration(job_in, plant_in); (only used with the Advanced Material Management Option) - Places all Lot IDs with expired dates older than the system date on Expired Hold.
AMMO only	CHECK PICK QUEUE - sdbp_check_pick_queue(job_in, plant_in); - (only used with the Advanced Material Management Option) - Recalculates pick queue status for checkout requests.
Receiving, Multi-Step Receiving, and Purchase Order modules	CHECK RECEIVED PO ITEM - sdbp_chk_issd_po_item - Sends an alert to the PO Item Requestor if the PO is fully received. This procedure looks for all issued PO records. For each PO line item with the field Receipts-Fully Received = Y, an Alert will be sent to the Requestor via the home page inbox. If the Requestor is invalid or null, a message will go to the job manager. The field Sent Alert Indicator on the PO Item is set to Y after an Alert/Job Log Message is sent. The Alert will only be sent once.
Approval Portal	CLEAR EVENT QUEUE - sdbp_event_queue.clear_events(job_in, plant_in); - Clears Event Queue records based on the setting of the Event Queue rule key in the Batch Purge Parameters Business Rule.
Work Order module	CLOSE WORK ORDER - sdbp_close_work_orders(job_in, plant_in); - Closes work orders in Finished status after the number of days specified in the WO Aging Business Rule.
Receiving and Multi-Step Receiving modules	COST ACCRUALS - sdbp_cost_accruals.cost_accruals(job_in, plant_in); - Accrues costs for receiving transactions that have not yet been posted. Information is selected from the table SA_RECEIVING_LOG and posted throughout the system as required.
Cost Adjustment module	COST ADJUSTMENT - sdbp_cost_adjustment(job_in, plant_in) - Processes adjustments costs that have not yet been posted.
Timekeeping, Direct Charges, and Service Request modules	COST AND CLOSEOUT - smu_interface.sdbp_mu_interface(job_in, plant_in, 'N'); - Processes transactions entered in cost and closeout.

Asset, Work Order Task modules	<p>COST ASSET - sdbp_cost_asset.cost_asset(job_in, plant_in) - Allocates costs to assets indicated on the Asset list in the Work Order Task module by creating cost adjustment records and posting accordingly. This functionality is only applicable when the Allocate Costs to Asset option in the Work Order Processing business rule is set to ON. You must either set the job run option to YES in the Batch Job Control business rule or set up an individual batch schedule for it to run automatically. The cost adjustment is not created until the work order is in closed status, so this should run after the close work order process. Please refer to the instructions under the Job Manager module for more information.</p> <p>One reason that you may not want to include this process in the general run all batch schedule is that your business process does not require that it run on as frequent or infrequent schedule as the jobs managed by Batch Job Control.</p>
Invoicing module	<p>COST INVOICE - sdbp_cost_invoice.cost_invoice(job_in, plant_in); - Processes costs for purchase Invoices, selecting approved Invoices and posting costs throughout the system as required. Once an Invoice is successfully processed, it is marked as posted.</p>
Work Order Task module	<p>COST LABOR - sdbp_cost_labor.cost_labor(job_in, plant_in); - Processes approved labor costs (from timesheets) that have not yet been posted. Costs are posted to the work order task as a Labor record. If a Labor Requirement record does not yet already exist for the task, the system inserts one, then posts the cost. Once a labor charge is successfully processed, it is marked as posted.</p>
Service Invoice module	<p>COST SERVICE INVOICE - sdbp_cost_service_invoice.cost_service_invoice(job_in, plant_in); - Processes costs for service contract Invoices, selecting approved Invoices and posting costs throughout the system as required.</p>
Service Request module	<p>COST SERVICE REQUEST - sdbp_cost_service_request.cost_service_request_rollup(job_in, plant_in); - Posts closed service request assets to the cost asset table.</p>
Storeroom module	<p>COST STOCK - sdbp_cost_stock.cost_stock(job_in, plant_in); - Processes costs for stock transactions that have not yet been posted. Information is selected from the table SA_INVENTORY_LOG and posted throughout the system as required. Once a stock cost transaction is successfully processed, it is marked as posted.</p>
Bill of Material, Master Catalog, and Asset modules	<p>CREATE BOM DETAILS - sdbp_create_bom_details.create_bom_details(job_in, plant_in); - Provides an automated means of updating existing bill of materials with new stock codes based on other operations occurring in the system. Stock Code is added to the BOM ID related to Asset ID/Component ID information selected from SA_INVENTORY_LOG and SA_RECEIVING_LOG tables. Once a log record is successfully processed, it is marked as complete.</p>
Asset, Fleet Asset modules	<p>DEPRECIATE ASSETS - sdbp_end_period_depreciation(job_in, plant_in); Depreciation costs are posted by batch according to settings in the Asset Depreciation Business Rule.</p>
Direct Charges module	<p>DIRECT CHARGES - sdbp_direct_charges.direct_charges(job_in, plant_in); - Processes approved Direct Charges costs which have not yet been posted, and creates new entries in the Direct Charges Log.</p>
Storeroom module	<p>END PERIOD DEPRECIATION- sdbp_end_period_depreciation(job_in, plant_in)(job_in, plant_in); - This will post Depreciation Costs according to settings in the Asset Depreciation Business Rule.</p>
Work Order and Work Order Task modules	<p>FINISH WO - sdbp_finish_wo(job_in, plant_in); - Updates the work order header status to Finished if either all associated tasks are in Closed, Canceled, or Finished status, or if the work order has no associated tasks.</p>

Regulatory Accounting module	FIXED ASSET VALUATION - sdbp_work_order.fixed_asset(job_in, plant_in); - Processes actual amounts and allocation amounts for a work order task and applies them to the Regulatory Accounts associated to the compatible units on the task. Also determines the value of fixed assets associated to the capital regulatory accounts on the work order tasks. This procedure also includes the package that creates change requests for the creation or retirement of group assets on a work order task.
Home Page	GENERATE ALL CHART IMAGES - sdbp_generate_all_chart_images (job_in, plant_in); - Generates chart images used on home page. . Run Now is not an option on the Actions list for this batch process. If you want to regenerate the thumbnail chart image on the spot, open the Charts Administration module, locate the chart on the list, and click the Regenerate Image button.
Work Order and Work Order Task modules	HELD FOR PARTS - sdbp_held_for_parts(job_in, plant_in); - Reviews work order task parts requirements vs. stock inventory and direct purchases for a task. If the On-Hand quantity in a storeroom is less than the amount required for an active task or if direct purchase items ordered for a task are still not received, the Held for Parts indicator on the task is checked. If all parts required (storeroom and direct purchase) are available, the Held for Parts indicator is unchecked.
Invoicing, Receiving, and Multi-Step Receiving modules	INVOICE RESOLUTION - sdbp_invoice-resolution(job_in, plant_in); - Uses the Invoice Setup Criteria Business Rule for determining whether mismatched invoice processing is allowed, and tries to resolve mismatched invoices to PO receiving.
Leave Request and Timekeeping modules	LEAVE REQUEST - sdbp_post_leave(job_in, plant_in); - Posts Leave Requests and creates timesheets for approved Leave Requests that have the Create Timesheet indicator checked and are in an open Pay Period.
Home Page	METRIC HANDLER - sdbp_metric_handler (job_in, plant_in); - Processes all metrics to get current data.
Payroll Voucher module	PAYROLL VOUCHER - sdbp_pay_voucher.pay_voucher(job_in, plant_in); - Processes approved payroll vouchers which have not yet been posted. Once a payroll voucher is successfully processed, it is marked as posted.
Pm Master, Work Order, and Benchmark modules	PM CYCLE - sdbp_pm_cycle_job.start_job(job_in, plant_in); - Reviews active PM Masters and cycles those that are due, creating work orders in the status defined in the PM Master Parameters business rule. If the PM is being cycled and the Benchmark's component is no longer installed on the Benchmark's asset, the system will generate a work order with the asset from the Benchmark and will not bring over the component.
PM Master and Work Order modules	PM FINISH - sdbp_pm_finish(job_in, plant_in); - Processes PM Master information for those PMs where the associated work order has been set to Finished status. This includes entering the work completion date, inserting a new Forecast record (to maintain the correct number of future Cycles), and setting any skipped Forecast dates to Canceled status. The Next Schedule Date is recalculated (for Calendar Interval PMs) and is placed on the PM Master record.
Schedule PM Route, PM Route, and PM Master modules	PM ROUTING - sdbp_pm_routing(job_in, plant_in); - Updates PM Stops based upon the Completed Dates entered on a Scheduled PM Route List. Next Schedule Dates are then adjusted as required and the PM Route Stop item is set to Posted.
Purchase Order module	PO CLOSEOUT - sdbp_po_closeout(job_in, plant_in); - Reviews Purchase Orders, setting the header status to Received, Fully , Invoice, Fully , or Closed as appropriate. Before a Purchase Order is set to Closed status, it must remain in Invoiced, Fully status for the number of days defined in the PO Aging Business Rule.
Timekeeping module	POST TIMESHEET - sdbp_post_timesheets.post_time(job_in, plant_in); - Posts timesheet information such as Comp Time, Leave, Regular Time, etc. for Pay Periods and recalculates the leave time balance. Once a Timesheet has posted for the Pay Period, the payroll status is set to Closed.

	<p>PROCESS FIXED ASSETS - sdbp_work_order.fixed_asset(job_in, plant_in); - Processes actual amounts and allocation amounts for a work order task and applies them to the Regulatory Accounts associated to the compatible units on the task. Also determines the value of fixed assets associated to the capital regulatory accounts on the work order tasks. This procedure also includes the package that creates change requests for the creation or retirement of group assets on a work order task.</p>
Service Timesheet, Work Order, and Work Order Task modules	<p>PROCESS SERVICE TIMESHEET (APPROVED TIME)- sdbp_process_service_timesheet.post_approved_time(job_in, plant_in); - Processes approved labor costs (from service timesheets) that have not yet been posted. Costs are posted to the work order task as a Labor record. If a Labor Requirement record does not yet already exist for the task, the system inserts one, then posts the cost. Once a labor charge is successfully processed, it is marked as posted.</p>
Project/Subproject module	<p>PROJECT ALERT - sdbp_project_alert.alert_job(job_in, plant_in); - Uses the Project Budget Options Business Rule for determining if a percent and/or dollar tolerance is to be used. The estimated and committed subprojects costs are compared to the budget amount minus the tolerance. An alert is sent to the subproject supervisor_name and to the project project_manager when these costs are above the target amount.</p>
System-wide	<p>PURGE DATA - sdbp_purge_data(job_in, plant_in); - Purges (deletes) data from database tables as defined in the Batch Purge Parameters Business Rule. Currently Alerts and Batch Messages are reviewed, deleting only those records that are older than the number of days defined in the rule for that item.</p>
Requisition and Purchase Order modules	<p>PURGE REQUISITIONS - sdbp_purge_requisitions.purge_req(job_in, plant_in); - Enable or disable a batch job to purge Requisitions in PO Created status where the PO is in a certain status. The status and age are defined in the Batch Purge Parameters and Batch Purge Criteria Business Rules.</p>
Work Order, Work Order History modules	<p>PURGE WORK ORDER - sdbp_purge_work_order.purge_wo(job_in, plant_in); - Selects the work orders that have been in Closed status for the number of days as defined in the Work Order Aging Rule, then copies them into the Work Order History tables. Each selected work order is reviewed to see how much information is to be moved to the History tables (defined in the Work Order Closeout detail). Asset History information is also inserted. Once a work order is successfully processed, the work order is deleted from the work order tables.</p>
Work Request and Work Order modules	<p>PURGE WORK REQUESTS - sdbp_purge_work_requests.purge_wr(job_in, plant_in); - Allows you to explicitly enable or disable a batch job to purge work requests in WORK ORDER status where the work order is in a certain status. Status and age are defined in the Batch Purge Parameters and Batch Purge Criteria Business Rules.</p>
Regulatory Account module	<p>REGULATORY ACCOUNT COST - sdbp_regulatory_account_cost(job_in, plant_in) - Posts costs associated to regulatory accounts.</p>
Work Order Task and Scheduling modules	<p>RESCHEDULE WORK- sdbp_reschedule.job_reschedule(job_in, plant_in); - Reviews all active work order tasks which are unfinished and places them on the Daily and / or Weekly Schedules as defined in the Auto Generate Daily Schedule and Auto Generate Weekly Schedule Rules. Work Order which were just generated by PM Master processing will also be placed on the Daily / Weekly Schedule.</p>
Storeroom, Work Order Task, and Work Order modules	<p>RESET DEMAND QUANTITY - sdbp_storeroom_demand(job_in, plant_in); - Recalculates the On-Demand Quantity for parts within the storeroom. This procedure reviews all active work order tasks, summing the quantities required across tasks for stock items. Once recalculated, the On-Demand Quantity for each storeroom item is updated accordingly. Note that this batch procedure is not a required procedure since standard processing maintains the storeroom On-Demand Quantity. This serves as an extra level of assurance that the On-Demand Quantities are correct as of each nightly batch run. Note that running this process could potentially be time consuming if there is a large amount of data for the system to process.</p>

Storeroom module	<p>RESET ON ORDER QUANTITY - sdbp_storeroom_on_order (job_in, plant_in); - Resets the quantity for storeroom parts that are on order. This procedure is triggered when a PO is canceled.</p>
Storeroom and Reorder Review modules	<p>STOCK REORDER - sdbp_stock_reorder.stock_reorder(job_in, plant_in); - Reviews all storeroom items, selecting those that are set up for automatic reorder and processes those items that have reached their reorder point. This process uses settings in the Batch Stock Reorder Business Rule to calculate the quantity to reorder. The basic calculation is:</p> $\text{reorder_quantity} = \text{maximum_quantity} - (\text{inventory_quantity} + \text{in receipt quantity} + \text{on_order_quantity} + \text{reorder_quantity} + \text{repair_quantity})$ <p>You can set a custom batch process to run SDBP_STOCK_REORDER on a specific storeroom by entering that storeroom in the job parameters.</p>
User-Profile module	<p>SYNCHRONIZE USER - sdbp_clean_user_n_user_profile (job_in, plant_in); - Synchronizes records in SA_USER and SA_USER_PROFILE by inserting missing user records for matching user profiles, setting a default plant if not specified, and deleting user records without matching user profiles.</p>
Warranty, Warranty Claim modules	<p>WARRANTY EXPIRATION ALERTS - sdbp_process_warranty_alerts(job_in, plant_in); - Sends alerts to the person indicated on the Warranty when the warranty expires.</p>
Regulatory Accounting and Account modules	<p>YEAR END OH DISTRIBUTION - sdbp_year_end_oh_cost_dist (job_in, plant_in); - Provides the ability to allocate costs from overhead regulatory accounts to the appropriate capital, maintenance and/or operations regulatory accounts at year-end.</p> <p><i>To Run Stock Reorder Batch Processing for a Specific Storeroom</i></p> <ol style="list-style-type: none"> 1. Open the Job Manager Search Options screen. 2. Select Create Job from the Actions list. 3. Enter the Storeroom in the job parameters. <p>For example: SDBP_STOCK_REORDER.STOCK_REORDER (9,'01', 'WH1'); where 9 is the job number, '01' is the plant and 'WH1' is the storeroom.</p> <ol style="list-style-type: none"> 4. Click the Save icon. <p>Doing this does not exclude the storeroom from the standard job that is completed with Run All Batch.</p> <p>UPDATE TEMPLATE STATUS - sdbp_update_template_status(job_in, plant_in); - Not Active.</p>
Vendor, Multi-Step Receiving, and Purchase Order modules	<p>VENDOR PERFORMANCE - sdbp_vendor_performance.vendor_performance(job_in, plant_in); - Supports the gathering of Vendor Performance statistics. This procedure performs the following:</p> <ul style="list-style-type: none"> • Identifies the processing parameters for the Current Rating Period for Active Vendors. • Updates Quality Performance data based on changes since the last batch run. • Updates Delivery Performance data for new transactions. • Updates Quality Performance data for new transactions.
Regulatory Accounting	<p>YEAR END OVERHEAD DISTRIBUTION - sdbp_year_end_oh_cost_dist(job_in, plant_in) Allocates costs from Overhead Regulatory Accounts to related non-overhead accounts (Capital, Maintenance, Operations, Work In Progress) based on Overhead Class.</p>

Additional Batch Jobs Not Included in Business Rule	
Invoicing module	AUTOMATIC INVOICING - sdbp_ers_invoicing(job_in, plant_in); - Generates invoices based on records that are set for automatic invoicing.
Cost Adjustment, Work Order Task, and PM Route modules	COST ADJUSTMENT FOR PM ROUTE - sdbp_cost_route.cost_route(job_in, plant_in); - Generates and posts cost adjustments to remove charges from the work order task account and distribute them among the PM Route's assets. Labor and material costs related to accomplishing the Scheduled PM Route are charged against the work order's task and then distributed amongst the assets that were finished on the PM Route.
Maintenance module	CREATE NEW LEAVE YEAR - sdbp_create_new_leave_year.new_leave_year(job_in, plant_in); - Inserts leave records once per year for all employee records into the Employee Leave detail, carrying over remaining leave information from the previous year.
System-wide	END OF PERIOD PROCESSING - sdbp_end_of_period_processing(job_in, plant_in); - Processes storeroom data at the end of each accounting period, populating the Storeroom Usage table and resetting the Storeroom Month-to-Date (MTD) Usage quantity to zero.
Home Page	GENERATE CHARTS - sdbp_generate_chart_image (job_in, chart_id_in, plant_in) - Generates specific chart images. For the chart identifier, this procedure uses only the number following "s_cht" in the chart name (for example, 140 is the chart_id for chart s_cht140). . Run Now is not an option on the Actions list for this batch process. If you want to regenerate the thumbnail chart image on the spot, open the Charts Administration module, locate the chart on the list, and click the Regenerate Image button.
Job Manager Log module	JOB MANAGER - sdbp_job_error_log ((job_in, plant_in, sysdate-365); - Generates entries in the Job Manager Log.
Requisition module	REQUISITION TEMPLATE STATUS CHECK - sdbp_req_template_status_chk(job_in, plant_in); - Changes the status of requisition templates to inactive when they reach the expiration date.
System-wide	RUN ALL BATCH - sdbp_run_all_batch(job_in, plant_in); - Calls all of the batch procedures defined in the Batch Job Control Business Rule. SDBP_RUN_ALL_BATCH generally includes all procedures that need to run on a daily basis. Procedures that need to run at different periodic intervals, such as once a year or at the end of the Pay Period should be scheduled separately.
	The order in which batch procedures are run makes a difference since a batch procedure may be dependent upon the data processed in another batch procedure. If they are run out of order, you may not see the data (such as cost roll-ups) for the batch run until the next time batch procedures are run.
Storeroom and Material Disposition modules	STOREROOM REPAIR COSTS - sdbp_storeroom_repair_costs(job_in, plant_in); - Sums costs based on the material and account log for material that has been dispositioned from closed work orders.

Reports

S_RPT097 - Job Manager Log Report

The report is designed to show the Job Manager Log detail log for the Job Manager. The report always uses the plant that is associated with the user.

Installation Parameters

BATCH JOB DEBUG MODE

ON/OFF

This parameter determines whether the dbms_activity will be appended to the messages in the Job Manager Log. The dbms_activity will not be appended if the value is set to OFF. A value of ON will do otherwise.

Approval Limit Module

Create and manage Approval Titles in the Approval Limit module. Approval Titles are used throughout the system to determine who can give approval for various kinds of documents (in the form of records). Examples of these documents include Purchase Orders, Requisitions, Work Orders, Work Requests, etc. In order to be able to approve a given type of document, the user must be assigned the appropriate approval title.

Users can have more than one Approval Title and any Approval Title can have more than one kind of document that it's users can approve as well as more than one user. Approval Titles also have a monetary limit for each document. For example user A, the Maintenance Department swing-shift supervisor, might have an Approval Title for all maintenance documents, and be able to authorize work requests up to five hundred thousand dollars, but only be able to approve work orders for one hundred thousand dollars or less.

Approval Titles can be combined to form Approval Routing Lists to manage the approval process when several individuals or departments must review records before final approval is granted.

Refer to the index under the "Approvals" topic to see where special considerations are needed for various modules and functionality.

Fields

Approval Title and Description

The Approval Title field indicates the code that is selected from the Next Approver field or the Approval Route field on records that require approval. Create Titles that are meaningful for the job function responsible for approving the records that will be designated under the Document type.

Type

Indicates the type of records that can be approved by this Approval Title. Type can be set to:

- **M** - for Maintenance Approver titles
- **P** - for Production Approver titles
- **B** - if the title serves for both Maintenance and Production Approver titles.

Employee Number and Username

The Employee Number field contains the Employee Number of the person being assigned the Approval Title. The field has an associated List of Values that is controlled by the Employee module in the Resource subsystem. When you supply the Employee Number, the system supplies the Username.

Alert?

If the Alert? box is checked the system sends an alert to the user when a document of the appropriate type and value needs to be reviewed or approved. By leaving the box blank, you can have a user be able to approve documents but not be alerted on a daily basis.

Active?

A check in the Active? Check box indicates that the Approval Title is active for that user. This allows you to easily deal with situations where a user periodically acts as a replacement in the absence of another user; the first user can be given all of the second user's Approval Titles and the titles need only be activated when the second user is away.

Document and Limit

The Document list indicates which record types the Approval Title can approve, while the associated limit represents the maximum monetary value of the record that can be approved.

Copy Record

APPROVAL - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Modules and Activities Requiring an Approval Title

The list of documents is controlled by system Code Table 184. This code table can not be modified. Approval Titles should be configured for each of the following modules (provided the module will be used in your business operations):

ADJUST - Cost Adjustment
CHNGASSET - Change Request - Asset
CHNGCATLG - Change Request, Catalog
CHNGGEN - Change Request - Generic
CHNGSTORRM - Change Request, Storeroom
CHNGVEND - Change Request, Vendor
CO - Change Orders
CONTIME - Service Contract Timesheet
DC - Direct Charges
INVC - Invoice
LEAVEREQ - Leave Request
ODCLOG - Direct Charges Log
PERMIT - Permits
PO - Purchase Order
PROC - Procedures
PROJECT - Project
REQSTN - Requisition
RFQ - Request for Quotes
SERVREQ - Service Request
TIME - Timesheets
WO - Work Orders
WOASSIGN - Work Order Task Assignment (obsolete)
WODESIGN - Work Design
WRKREQ - Work Requests

Approval Titles should also be configured to approve any of the following activities that will be necessary in your organization:

AVOVERRIDE - Approved Vendor Override
DISCRPACT - Discrepancy Activity (obsolete)
DISCRPOWN - Discrepancy Owner (obsolete)
INSPECTION - Inspection Owner (obsolete)
MATLPLAN - Material Planner (obsolete)
PHYSWZRD - Physical Inventory Wizard
TIMEWZRD - Timesheet Wizard

Routing List Module

Routing Lists work in conjunction with Approval Titles, which are managed in the Approval Limit module. Approval Titles are used throughout the system to determine who can give approval for various kinds of documents (in the form of records). Currently, Routing Lists only apply to Requisitions, Purchase Orders, Change Orders, Change Requests and Work Order Material Detail Direct Purchases.

Fields

Title

The Approval Title from the Approval Limits module.

Description

The Approval Title description from the Approval Limits module.

Sequence

The sequence that the Approval Title occupies in the route.

Mandatory

Checked, this box indicates that the Approval Title cannot be skipped. If an Approver disagrees with an item sent through Approval Routing, this stops the process.

Notify Only

Checked, this box indicates that the Approval Title will merely get an Alert to agree or disagree and this Approval Title can be skipped. If an Approver disagrees with an item sent through Approval Routing, this will not stop the process.

If both the Mandatory and Notify Only fields are left unchecked, the approver listed will receive an alert, but his or her response will not affect the approval route.

Business Rules

Approval Routing Rule

The screenshot shows a configuration window titled "Business Rule APPROVAL ROUTING". It contains the following fields and sections:

- Rule ID:** APPROVAL ROUTING
- Business:** Business
- Parameter:** Parameter
- Limit?:**
- Desc:** This rule defines options for Approval Routing.
- Comment:** (Empty text area)
- Table:** A table with two columns: "Key Name" and "Option".

Key Name	Option
EMAIL CONTENT TYPE	URL
USE ASSOCIATED DOCUMENTS	OFF
- Description:** This key specifies the content type to be used for e-mail generation and is only valid with the key value 'EMAIL INTEGRATION' is set to 'ENHANCED' in the 'EMAIL CONFIGURATION' Business Rule.

Determine how the system routes Alerts for documents requiring approval.

Key Name and Option

APPROVAL ALERT NAVIGATION - When this rule key is set to WIZARD, clicking on an alert opens an approval wizard to guide you through the approval process. If the rule key is set to RECORD, clicking on an approval alert opens the record. Note: Alerts will open

according to how this rule key was set when the alert was generated. For example, if users have existing alerts and you change the setting from RECORD to WIZARD, those existing alerts will still open the record, but alerts created after the rule key change will open the wizard.

EMAIL CONTENT TYPE - This key specifies the type of e-mail content allowed when e-mails are sent from Oracle Utilities Work and Asset Management to a regular e-mail program. This key is only valid when the EMAIL CONFIGURATION BUSINESS RULE has the key value 'E-MAIL INTEGRATION' set to ENHANCED. Options include:

EMBEDDED URL - URL links are specified in the e-mail body.

HTML - Included in the e-mail body.

TEXT - Only Text is included in the e-mail body.

URL - URL links are included at the end of the e-mail body.

USE ASSOCIATED DOCUMENTS - This key determines whether the Approval Routes can be associated with document types. Set to ON to make the Associated Document view available in the Routing List module and to have Approval Routing LOVs reference the document types entered on that view.

Batch Processes

Clear Event Queue - `sdbp_event_queue`;

Clears Event Queue records based on the setting of the Event Queue rule key in the Batch Purge Parameters Business Rule.

Copy Record

ROUTELIST - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Process flow:

Approval Routing
Change Record's Status from Pending Approval to Approved



Confidential © 2007 Oracle Corporation
 Quyen Pham
 Created Date: Nov. 2, 2006
 Last Updated Date: Feb. 1, 2007

Chapter 2

Administration Subsystem

The Administration subsystem is primarily reserved for working with database settings. You can use the Administration subsystem to set up user profiles, describe how your organization's business practices work within the system, and much more.

Most users will use the Administration subsystem for changing their user profiles and for establishing WorkFlow Groups. Access to most of the other modules is usually restricted to a limited number of users or to the system administrator and the database administrator only.

Business Rules Module

There are many functions and features built into the system that can be configured through rules to meet your business requirements. Business rule settings determine processing functionality in the application, without requiring overall program changes. The system uses business rules to create system flexibility without having to recreate the software for each organization.

Users can not create new rules. However, application users with the proper authorization can change Rule Types, descriptions, comments, parameters, and list items.

Business rules vary in their nature, some control how the system processes information, others store default information and parameters. For any given rule you enter parameters or set the Options Status to ON or OFF, YES or NO to activate or deactivate it.

All of the business rule list items and parameters should be set by a system administrator during the set up phase of the system package.

Caution: Once these business rules have been set with the help of a Business Analyst, they should only be changed after careful consideration and consultation with Oracle Utilities Work and Asset Management. Improper changes can disrupt how the system processes your organization's information.

Rule ID

Each business rule is delivered with a unique Rule ID.

Rule Type (First Unlabeled Field)

There are three types of business rules. While these distinctions are primarily to help in searching for specific groups of rules you should not change the rule type without very careful consideration.

BUSINESS - Rules that model specific Business Practices of multiple organizations across several industries. By setting these rules properly you can replicate many of the specific practices of your organization. An example would be settings governing how inventory is conducted.

CONFIGURATION - Rules that affect how the system behaves without affecting processing that affects your organization's Business Practices. An example would be how drill-down behaves for users.

CUSTOM - Rules that are customized specifically for your organization. An example would be configuring the interface between the Oracle Utilities Work and Asset Management system and your organization's General Ledger application.

Rule Style (Second Unlabeled Field)

There are two basic 'styles' of business rule:

PARAMETER - Rules that govern processing such as defining how long a specific document should age before being purged from the system or archived.

LIST - These Rules provide a way to associate items, such as usernames, with processing. For example determining which users should be granted access to pay rate information.

Limit?

A check in the Limit? check box indicates that the business rule will not be updated by installation of new releases.

Note: As new functionality is added to the system, we must sometimes change or add to business rules. While we try to ensure that these changes will not negatively affect users, this is not always possible. To avoid this situation you can elect to protect a business rule

from update in future releases and service packs by checking the Limit? check box and clicking the Save icon on the toolbar.

Description and Comment

The Description and Comments give information about the business rule and how it should function. Words from the Description can be used on the Business Rules Search Options window to help find a given rule. The Comments field usually contains notes about the Rule's keys which are displayed in the lower section of the window.

The Rule "Keys"

The upper section of each Business Rule window remains constant from business rule to business rule. The lower section of each Rule contains the Rule's keys. These sections vary greatly. For more information on a rule key please refer to the individual rule description.

Reports

S_RPT002 - Business Rule Report

Lists all of the business rules in the Business Rule module under System Configuration in the Administration subsystem

Custom Rules

Some business rules that appear in the system are tailored for specific clients, interfaces, or other specific needs. In general you can disregard these rules during your configuration session.

ACCOUNT RULES - This custom rule is used by a client-specific interface routine and is not applicable for general use.

ANALYSIS VIEWS ACCESS LIST RULE - This rule is used in conjunction with customized functionality which enables linking of Oracle Utilities Work and Asset Management and Microsoft Excel spreadsheets. In order to use this functionality, you must run sql scripts (provided by Oracle Utilities Work and Asset Management), and store the excel spreadsheets in a networked location.

The business rule is used to MANAGE (not create) the users that are created using the script. Once the script is run, it populates the business rule, and at that point you can assign additional plants to those users, or reassign their plants. The users created in the script act like "dummy" users for each plant. I.e., standard usernames and passwords cannot be used when executing "refresh data" in Excel.

Your system administrator should work with a Oracle Utilities Work and Asset Management representative to configure and implement this functionality.

AP BATCH INTERFACE RULE - This rule is used to set up processing for an Account Payable interface. AUTO GENERATE AP_BATCH_NO: Enter ON in the OPTION STATUS column to allow Account Payable batch numbers to be generated from the Ready for Payment Report (Report 63 in the Administration module, Report Administration). Enter OFF in the OPTION STATUS column to disallow Account Payable batch numbers to be generated.

EDI TRANSACTION CODES RULE - Defines the transaction codes and their relationship with modules.

GIS ASSET INTERFACE - This rule shows the list of GIS Views to be processed by the GIS Asset Interface. The GIS View must match SV_GIS_ASSET_LAYOUT. GIS View records will be copied directly to SA_ASSET. GIS Table will be updated with the newly created Asset ID (ASSET_RECORD_TYPE - ASSET_ID).

GIS SETUP RULE - This rule defines which GIS tool is to be used with Oracle Utilities Work and Asset Management. Setting the ACTIVATED GIS OPTION rule key to ORACLE1 prompts the system to use the integrated GIS Viewer which is licensed separately, but can be accessed from the Home Page. Please review the relevant documentation for settings related to external third party options such as ESRI, Intergraph, and Autodesk.

GIS SPECIFICATION INTERFACE - This rule shows the list of GIS Views to be processed by the GIS specification interface. GIS View must match SV_GIS_SPECIFICATION_LAYOUT. GIS View records will be copied directly to SA_SPECIFICATION. Then the GIS Table will be updated with the newly created Specification ID (SPECIFICATION_RECORD_TYPE - SPECIFICATION_ID).

GIS View must contain SYNERGENID. All other fields should have the following format: "spec_seq_no-" || GIS_FIELD Example: "1-" || pipe_length

GIS VIEW ATTRIBUTES - Defines Asset Type Views to be used by GIS (e.g. Manholes, Pipes, Hydrants, Valves, etc). The views are custom and need to be created per Asset Type. This rule is intended for custom use with GIS. Please contact your Project Director for configuring setup.

INTERFACES - Allows you to explicitly include or exclude specified interfaces from interface processing. If this rule is set to "ON", then the interface table listed will be populated with data rather than the normal processing associated with the interface point. For example, if SA_REQUISITION_INTERFACE is set to "ON" then when REQUISITION_STATUS is changed to PO CREATED the interface table is populated and the purchase order record is not generated.

ORACLE CAI FINANCIALS ADMIN - Used to control functionality related to the Financials Option2, Oracle Financials CAI Interface.

ORACLE FINANCIALS - Turns on and off various interfaces to Oracle Financials (version 9.x).

ORACLE PURCHASING - Controls various interfaces to Oracle Financials (version 9.x) Purchasing.

OUBI SETUP RULE - Business Intelligence. Configure settings to determine which extracts will be completed during regular processing. This rule can also be used to define extraction details such as data source, file names and the output directory. If desired, any extract can be turned OFF so that it is not included in the overall extraction. Please refer to the [Business Intelligence](#) guide for more information.

REPORT LABELS - Controls labels for custom reports. Is not applicable to general users.

RFGEN BARCODING SETUP - Used to set up barcoding processing using RFGen network. Please refer to the [Barcode User Guide](#) for more information.

SAIF CHARGE NUMBERS INTERFACE - Allows you to include or exclude particular charge numbers from populating the SAIF_CHARGE_NUMBERS table. This rule applies to the following modules: Asset, Function, Process, and Work Order Task.

TIMEKEEPING DTA PAY CODE - Sets up parameters for the pay codes defined in Code Table 72. This rule is used with a client-specific interface routine and is not applicable for general use.

TIMEKEEPING DTA REGULAR TYPE - Sets up edit checks for timekeeping. Note: This rule is used in conjunction with a client-specific interface routine and is not applicable for general use.

Integration Rules

The following business rules must be configured to facilitate interfaces between Oracle Utilities Work and Asset Management and other products. Unless your organization uses integrated products, you can disregard these rules during your configuration session.

Please contact Oracle Utilities Work and Asset Management for more detailed documentation.

PRODUCT INTEGRATION - This rule defines the type of integration that is being used with the system. Point to Point indicates that Oracle Utilities Work and Asset Management is integrated with only one other product. Field Work indicates that Oracle Utilities Work and Asset Management is integrated with both Oracle Utilities Mobile Workforce Management and Oracle Utilities Customer Care and Billing.

PRODUCT INTEGRATION CCB CONTACTS - Customer Contacts can be generated in CCB upon creation or update of a CCB Field Activity from Service Requests. The Gen Contact column identifies whether the Customer Contact is generated or not. The Contact Type and Contact Class correspond to the values to be used for the Customer Contact and should be populated with values that have been established in CCB. The description field contains the text to be used for the Customer Contact description. The Trigger To Do field identifies whether a To Do is generated along with the Customer Contact. The Trigger Days and To Do Role fields are used to identify the time frame to generate the To Do and the user role to receive the To Do.

These rules must be set before inserting or updating of service requests tied to CCB Field Activities.

PRODUCT INTEGRATION CCB - Used to define values for the CCB Integration Interface. Refer to the CCB Integration Guide for more information.

PRODUCT INTEGRATION CCB FA TYPES - Used to define values for the CCB Integration Interface. Refer to the CCB Integration Guide for more information.

PRODUCT INTEGRATION CCB STATUS - This rule maps Oracle Utilities Work and Asset Management Service Request statuses to equivalent CCB Intermediate statuses. Only Service Requests with mapped CCB Intermediate statuses are included in integration file updates.

PRODUCT INTEGRATION FIELD WORK - Designates the parameters to be used when service request and customer records are created from interfaced records.

STANDARD SERVICE REQUEST INTERFACE - This business rule controls the fields that will be updated on an inbound service request record that already exists in Oracle Utilities Work and Asset Management. For each column name, indicate whether or not the corresponding field should be overwritten during an update.

WEB SERVICES GATEWAY - This rule controls settings for outbound message processing. The parameters set here determine how Oracle Utilities Work and Asset Management communicates with web services in other systems.

Web Service Gateway Key - References the services that Oracle Utilities Work and Asset Management can interface with.

Username and Password - The login needed to access the application referenced in the Web Service Gateway Key column.

Dataset ID - These values tell Oracle Utilities Work and Asset Management which table to retrieve information from, and provide the keys to use from that table. For

CC&B and FW the keys must also be configured on the other application as well as here.

Consumer Class - The Consumer Class column indicates the java class name called by Oracle Utilities Work and Asset Management.

Service URL and Gateway URL - The service URL column indicates the URL that the consumer class indicated in the previous column uses to call the other system. Gateway URL indicates the SIA web services server. The Consumer Class should be stored on this server. Use the IP address to indicate the service URL for both columns.

Interface Rules

Interface business rules specify the fields that are updated during interface transactions within the various modules where they apply. Interface settings are described in more detailed in the [Interfaces Guide](#).

In addition, the [Interfaces Rule](#) and the [Interface Parameters Rule](#) provide general interface settings.

- Account Interface
- Accrual Interface Rule
- Asset Interface
- Catalog Interface
- Customer Address Interface
- Customer SA Interface
- Customer Interface
- Default Accts for Interfaces
- Employee Interface
- GL Transaction Interface
- Manufacturer Vendor Interface
- Service Request Interface
- Storeroom Interface
- Vendor Interface

Interfaces Rule

(Custom)

This rule explicitly includes or excludes specified interfaces from interface processing.

Interface Rule and Option Status

Enter the interface program names to be included or excluded from interface processing in the Interface rule. The Option Status column should be set to ON or OFF to include or exclude the routine from interface processing. If an interface routine is not listed here but exists as a part of the interfaces which make up interface processing, by default, the interface will be included during processing.

For example, if SA_REQUISITION_INTERFACE is set to “ON” then when REQUISITION_STATUS is changed to “PO CREATED” the interface table is populated and this applications Purchase Order is not generated. Interface settings are

described in more detailed in the Interfaces Guide.

Interface Parameters Rule

This rule contains parameters that drive business logic in different interfaces. The [Interfaces](#) Guide provides additional information regarding specific interfaces.

Para Name and Param Value

ASSET ADDRESS PARSER & CUSTOMER ADDRESS PARSER - These rule keys are used with CCB Integration. The stored procedure entered in the Param Value field transforms address information coming from CC&B so that the information conforms to the fields in WAM.

In WAM parts of an address (Street Number, Street Name, Street Suffix and Apartment Number) are stored in individual fields. CC&B does not store addresses in such detail, rather it stores entire lines of addresses in Address 1, Address 2, and so on.

The parameter entered for these rule keys controls how address parsing occurs when the system processes customers, premises & service points. You can replace the standard batch job procedure with a custom procedure that uses the same parameters. The provided parameter parses out street number and name.

INVENTORY INTERFACE HANDLING - This key determines account and expense code handling for the WIFP_INVENTORY_LOG_INTERFACE. If the Param Value is set to OLD, the system uses the account from the referenced work order task and the expense code from the storeroom. If the Param Value is set to NEW, the system uses the values from the interface table. When NEW processing is used, the action type must also be set to 'P'. This setting can be accessed in WAIF_INVENTORY_LOG.

INVOICE STATUS - This key specifies the valid status for invoices sent out from the application. The default is POSTED.

Obsolete Rules

The following business rules are no longer used in the system. Many of them have been replaced, or are simply no longer in use.

- Barcode Label Printers
- Stores Transaction Groups - formerly used for BI processing. No longer used.

Advanced Materials Management Option (AMMO)

In prior releases the Advanced Materials Management Option (AMMO) was included as an extension to the system providing processing related to stock tracking, inspections, and discrepancy reporting. These options are not available in this release, however, some code tables and business rules remain in the system as artifacts of this additional processing.

- Bin Quantity Tracking Options
- Inspection Report Generation
- Internal Tracking Options
- Quote Options

AMMO Sequence Numbering Tables

- SA_ASSET_INSPECTION_DETAIL
- SA_BIN

-
- SA_BIN_RELOCATION
 - SA_INSPECTION
 - SA_INSPECT_TEMPLATE
 - SA_INTERNAL_TRACKING
 - SA_INVENTORY_LOG
 - SA_RETURN_REQUEST
 - SA_STOREROOM_REORDER_HISTORY
 - SA_DISCREPANCY

Buyers Module

Buyers have duties that are different from those of many other job titles within an organization. You can use the Buyers module of the Administration subsystem to define and assign those duties for individual users.

Each buyer has a unique buyer code. A list of values is available for the Username, drawing information from the User Profile module of the Administration subsystem. When you select a Username, the system supplies the user's name, phone number and fax number from the User Profile.

Fields

Stores Reorder

Check the Stores Reorder box to authorize a user to review and authorize Requisitions and Purchase Orders created by the system based on ABC Processing for Storeroom records.

Update Approved PO

Check this box to authorize a Buyer to modify Purchase Orders that are in Approved status.

Update Issued PO

Check this box to allow Buyers to cancel Line Items on Purchase Orders in Issued status as long as the Line Items do not have any receipts posted against them.

1. If the Update Issued PO authority is given to a Buyer it bypasses the standard Approval Process and allows them to update the value of the Purchase Order without validating the buyer's Approval Limit.
2. Also, buyers who have this authority do not need to create Change Orders or Expedite PO records. They can simply make the changes directly on the PO by changing the status of the PO to Updating and when the status is changed back to Issued the system automatically creates Change Order and/or Expedite PO records in the background as appropriate to the changes made to the PO. These backup records allow for standard audit tracking of all changes made to the Purchase Order record.

Code Table and Codes Module

The system uses code tables to validate user-entered information throughout the system. Generally, when a user clicks on the List of Values button for a field in a given module, the system presents the list of codes from the appropriate code table. Each code table consists of a unique number, a table description, and a list of codes and code descriptions.

Occasionally, the available code table will not meet the needs of your organization. In these cases, it is possible to create custom lists of values which do not use the standard code tables. Some custom lists of values can be created based on User-Defined fields (UDFs). However, most custom lists of values will require referring to the software code and should only be considered with the help of.

Fields

Table Number

This field holds a unique number that identifies the table. Table numbers 1 to 2000 are reserved for the system and you should not create tables with numbers in that range. It is recommended that all custom codes be created as 3000 and above.

Description

A short description of the table. This description is searchable and displays on the Results of Search window.

Type

There are 3 types of code tables in the system. Some users may have the ability to change Code Table types depending on the authorities that you have granted within the system. You should not change any Code Table types without very careful consideration as making such a change may impact the entire system.

USER - Codes Tables that can be added or modified by users with the appropriate Responsibilities assigned in the Responsibilities module of the Administration subsystem. Codes over 2000 are reserved for user-defined code tables.

DBA - Code Tables that can only be modified by the Database Administrator. The entered information impacts how the application functions and should be modified only by someone who is aware of how changes impact the system. Codes 1999 and below are reserved for System and DBA code tables.

SYSTEM - Code Tables that can be accessed by system users, but can not be modified by anyone other than Oracle Utilities Work and Asset Management Development. These code tables and their Codes are necessary for the application to run properly. Any questions or concerns about these code tables should be directed to the Database Administrator (DBA). Codes 1999 and below are reserved for System and DBA code tables.

Code Length

The Code length indicates the maximum number of characters that can be used in any code in the table. Changing the Code Length does not affect the display of the code in the list of values.

Code

The individual code name. The systems checks to make sure that the code is unique within the table (but not from one table to another) when you save the Code record.

Note: You can not modify a Code value once you have saved it. Make sure to only develop codes that will support your organization's Business Practices.

Description

This Description field contains a short description of the code. The system displays this

text beside the code on the List of Values, and can be searched using the Find button on the List of Values window.

Link

This feature is used in situations where the value entered into one field determines which Code Table to use for the following List of Values. For example: in the Commodity Codes view in the storeroom module of the Resource subsystem, the value you enter in the first field (Category) determines which Code Table to use for the next field (Name). Each Code entered into the Category Code Table has a Link value identified, linking several Commodity Name code tables to the Category Code Table.

Reports

S_RPT015 - Code Table Definition Report

Lists all of the code tables defined in the Code Table and Codes module of the Administration subsystem. This report has no Code Table Values.

S_RPT001 - Code Table Report

Lists all code tables and the Code Values as defined in the Code Table and Codes module, Administration subsystem.

System Code Tables

These code tables contain values that affect system functionality. The codes cannot be modified, but you can change the code descriptions if necessary.

- Code Table 0: Yes/No
- Code Table 1: Work Order Type Codes
- Code Table 19: PM Frequency Codes
- Code Table 15: Country Codes
- Code Table 30: Runtime Codes
- Code Table 34: State or Province
- Code Table 35: Category Codes
- Code Table 36: Consumables Category
- Code Table 50: Duration Units
- Code Table 60: Direct Charge Units
- Code Table 64: Form Function Types
- Code Table 65: Purchasing Vendor Characteristics
- Code Table 66: Approval Types
- Code Table 71: Work Types for BI Integration
- Code Table 74: Street Directions
- Code Table 79: Physical True Count Item Status
- Code Table 93: Report Output File Formats
- Code Table 94: Report Called By Modules
- Code Table 142: Tracking Transaction Codes
- Code Table 143: Receiving Transaction Codes
- Code Table 144: Inventory Transaction Codes

-
- Code Table 145: Stores Transaction Codes
 - Code Table 146: Account Log Transaction Codes
 - Code Table 148: Bin Transaction Codes
 - Code Table 149: Requisition Types
 - Code Table 151: Purchasing Item Types
 - Code Table 155: Purchase Order Types
 - Code Table 158: Invoice Pay To Vendor Indicator Values
 - Code Table 180: Standard Note Document Types
 - Code Table 184: Approval Document Types
 - Code Table 185: Approval Routing Document Types
 - Code Table 193: Pm Forecast Adjustment Codes
 - Code Table 204: Shelf Life Units
 - Code Table 229: Non-Equipment Asset Record Types
 - Code Table 286: Account Treatment Type
 - Code Table 287: Tracking Method
 - Code Table 288: Assessment Status
 - Code Table 289: Service Request Status
 - Code Table 290: Storeroom Auto-Reorder Sources
 - Code Table 291: Work Status
 - Code Table 292: Condition Rating Basis
 - Code Table 293: Delivery Lead Time Units
 - Code Table 294: Folders
 - Code Table 295: Item Type
 - Code Table 296: Req Status Type
 - Code Table 297: Rfq Status Type
 - Code Table 298: Downtime Indicator
 - Code Table 299: Weekly Schedule Indicator
 - Code Table 300: Daily Schedule Indicator
 - Code Table 301: Held For Parts Indicator
 - Code Table 302: Change Request Indicator
 - Code Table 303: PO Status Type
 - Code Table 304: Asset/ Fleet
 - Code Table 450: Standards Categories
 - Code Table 800: Graph Colors
 - Code Table 1110: Schedule Plan Summary Label
 - Code Table 1199: Days of the Week

DBA Code Tables

These code tables can only be modified by the Database Administrator. The entered information impacts how the application functions and should be modified only by someone who is aware of how changes impact the system.

- Code Table 095: Report Selection Block File Locations
- Code Table 096: Report Group
- Code Table 097: Report Types
- Code Table 156: Invoice Check Codes for AP Processing
- Code Table 187: Inventory Adjustment Reasons
- Code Table 188: Manual Hold Adjustment Reasons
- Code Table 251: Personal ID (Account Segment 1)
- Code Table 252: Area/Dept? (Account Segment 2)
- Code Table 253: High Level (Account Segment 3)
- Code Table 254: Mid Level (Account Segment 4)
- Code Table 255: Low Level (Account Segment 5)
- Code Table 256: Flex (Account Segment 6)
- Code Table 257: Account Number = (Account Segment 7)
- Code Table 258: Account Number = (Account Segment 8)
- Code Table 259: Account Number = (Account Segment 9)
- Code Table 260: Account Number = (Account Segment 10)
- Code Table 341: FMEA Template Severity Code
- Code Table 342: FMEA Template Occurrence Code
- Code Table 343: FMEA Template Detection Code
- Code Table 451: Unit Code (Asset Segment 1)
- Code Table 452: System Code (Asset Segment 2)
- Code Table 453: Designator Code (Asset Segment 3)
- Code Table 454: Asset Segment 4 (Asset Segment 4)
- Code Table 455: Type (Asset Segment 5)
- Code Table 456: Asset Segment 6
- Code Table 457: Asset Segment 7
- Code Table 458: Asset Segment 8
- Code Table 459: Asset Segment 9
- Code Table 460: Asset Segment 10
- Code Table 560: Workshop Codes
- Code Table 561: Subsystem Codes
- Code Table 562: Module Codes
- Code Table 563 - Function Codes
- Code Table 564: Decision Status Codes

-
- Code Table 565: Priority Codes

Obsolete Code Tables

The following code tables are no longer used in the system. Many of them have been replaced (as noted), or are simply no longer in use.

- Code Table 5: Permit Types (Obsolated by the Permit Types Business Rule)
- Code Table 11: Vehicle Classes (Vehicle classes are defined in the Asset Class module)
- Code Table 21: Printer Names for Report Processing
- Code Table 27: Work Codes (Obsolated by Code Table 13)
- Code Table 33: Blanket Purchase Order Types (Replaced by Code Table 151)
- Code Table 47: Service Contract Rate Types
- Code Table 72: Timesheet Regular Time Types
- Code Table 90: Project Types (Obsolated by Project Work Order Account Business Rule)
- Code Table 92: Invoice Item Types
- Code Table 103: Required Documentation Types
- Code Table 104: Currency Code (Obsolated by the Currency Exchange Rates module)
- Code Table 133: Engineering Specification Linked Pseudo Codes
- Code Table 135: Assigned Planner (Obsolated by the Planner Business Rule)
- Code Table 176: Expense Report Category
- Code Table 191: Work Order Job Codes (Obsolated by Code Table 190)
- Code Table 205: Route Description Code
- Code Table 206: PM Route Types (Obsolated by Code Table 20)
- Code Table 210: Currency Codes (Obsolated by the Currency Exchange Rates module)
- Code Table 220: Drawing Types
- Code Table 340: PM Master Units (Obsolated by Code Table 107)
- Code Table 600: Asset Class (Not Used - Codes are created in the Asset Class module.)

Advanced Materials Management Option (AMMO)

In prior releases the Advanced Materials Management Option (AMMO) was included as an extension to the system providing processing related to stock tracking, inspections, and discrepancy reporting. These options are not available in this release, however, some code tables remain in the system as artifacts of this additional processing.

- Code Table 140: Return Problem Codes
- Code Table 192: Supplier
- Code Table 194: Action
- Code Table 195: Problem Trend

-
- Code Table 196: Category Trend
 - Code Table 197: Group Trend
 - Code Table 199: Disposition Trend
 - Code Table 201: Quantity Classes
 - Code Table 214: Inspection Types
 - Code Table 215: Inspection Category
 - Code Table 320: Facility Types
 - Code Table 321: Bin Types
 - Code Table 322: Bin Level
 - Code Table 323: Bin Storage Types
 - Code Table 324: Bin Orientation
 - Code Table 325: Bin Document Types
 - Code Table 361: EDI Transaction Types

Configuration Guide Module

The Configuration Guide module is used during the set up of the system to help System Administrators (SA), Database Administrators (DBA), and Business Analysts (BA) keep track of which parts of the system have been configured as the system is being installed. The rows and columns are set up much like a standard spreadsheet where any data can be sorted, added, deleted, or updated. You can order data by any column in either ascending or descending order, or rearrange the layout of the columns to meet your specific needs.

You can also add rows to the Configuration Guide by highlighting a line and clicking the New icon. A row can be deleted by highlighting the row and clicking the Delete icon. Update any information on the screen by entering the desired data in the field and clicking the Save icon.

Note: There is more information than can be displayed on the screen at one time. Use the scroll bar located at the bottom of the window to scroll left and right to see the rest of the data.

The configuration of this item will be handled by the Oracle Utilities Work and Asset Management team and updated according to decisions made throughout the configuration workshops.

Code Tables

Code Table 560 - 565: Configuration Codes

Code tables 560 - 565 are DBA type code tables that define the modules, functions, subsystems, priorities, and decision statuses that are used in the Configuration Guide module.

Currency Exchange Rates

Currency codes and exchange rates are entered on purchasing documents to calculate the appropriate procurement costs. To establish the default code to be used in most instances, enter a code in the Local Currency field on the Plant record.

Fields

Currency

Create unique currency codes as appropriate to your business needs.

Effective Date, Exchange Rate, and Comments

Exchange Rates can be entered manually with comments as they change. The system defaults the current date for the Effective Date, but this can be changed if necessary.

Fine Grain Access Module

Use Fine Grain Access to extend security beyond the levels permitted in the Responsibilities module. Fine Grain Access operates during searching to restrict the records that individual users can see. For example, Fine Grain Access could be used to allow users to access only the work orders for their department or only the Purchase Orders they have created. An additional 'where clause' that is applied to all database queries the user runs against the table identified in the FGA record is required. The where clause is written as a SQL selection criteria statement. Fine Grain Access is invisible to the user and is enforced regardless of how the data is accessed.

Assigning Fine Grain Access is a two-part process. First the security policy is defined in the Fine Grain Access module, then it is assigned to users in the FGA Responsibility module.

As with other responsibilities, you must be careful not to group conflicting FGA conditions within the same FGA Responsibility. It is always a good idea to test FGA Responsibilities before releasing them to insure that they work in the manner you intended.

Note: Fine grained access processing cannot be used to restrict access to the Fine Grain Access module itself. If this configuration is an absolute requirement, you do have the option of creating custom tables to store fine grained access information. With this you must also write a stored procedure to restrict access to SA_USER_FGA_RESPONSIBILITY based on setup of these custom tables

Fields

Sequence No.: FGA ID

The record number is comprised of a unique ID (Ex. "ACCESS FGA1"). FGA record numbers are typically set to be user defined.

TABLE NAME - A_FINE_GRAIN_ACCESS - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Status

Active - FGA records are created in Active status.

Inactive - FGA records in Inactive status cannot be assigned in the FGA Responsibility module. If a control is not currently needed, but may be needed in the future, setting it to Inactive status avoids the need to re-input the record later.

Description

You can enter a description to help identify the FGA. The first portion of the description appears on the Search Results list when you are searching the Fine Grain Access module and also in the FGA Responsibility module when you are adding a FGA record to a responsibility.

Owner

Select the name of the person responsible for the access level from the List of Values. Owner is one of the values you can specify when searching the Fine Grain Access module.

Table Name

All Fine Grain Access records must reference a table in the system. When a user with a specific FGA Responsibility in their User Profile executes a query against the table, the additional where clause is executed.

Condition

Enter the where clause fragment (without the "where" keyword) using SQL that the system will add to queries the user executes against the table name specified Use the following example as a guideline:

1. Goal: Completely restrict account number access by user based on department.
2. Account number table is SA_ACCOUNT_DATA in schema WAM.
3. Create a policy on the SA_ACCOUNT_DATA table (see below for SQL Policy create statement).
4. Create FGA object for SA_ACCOUNT_DATA table using "Condition" with where clause "department in (1, 2,3)."
5. Assign FGA object to appropriate users.

```
Execute DBMS_RLS.ADD_POLICY(  
object_schema => 'SYNERGEN',  
object_name => 'SA_ACCOUNT_DATA',  
policy_name => 'ACCOUNT_SELECT',  
function_schema => 'SYNERGEN',  
policy_function =>  
'sdbp_fine_grain_access.fine_grain_generic_retrieval',  
statement_types => 'SELECT,INSERT,UPDATE,DELETE'  
);
```


FGA Responsibility Module

Administrators can use Fine Grain Access to extend security beyond the levels permitted in the Responsibilities module. While Responsibilities can restrict the modules and functions available to users, Fine Grain Access operates during searching to restrict the records that individual users can see.

Views

Assign a FGA Responsibility to users in the Assigned Users view. This view allows you to make several assignments at the same time. The alternative is to assign FGA Responsibilities through the FGA Responsibility view of the User Profile module in the Administration subsystem.

Assigned Users



Help Form Module

The Help Form module in the Administration subsystem maintains the context sensitive links between the Oracle Utilities Work and Asset Management application and the online Help file. Context sensitivity is what makes online Help open to discussion about the particular screen you are viewing when you select online Help. The links are established by assigning a unique online Help topic (.htm page) to each form and block combination in Oracle Utilities Work and Asset Management. A stored procedure determines if a user guide, cue card or tutorial topic opens, depending on which option you select from the main Help menu. Oracle Utilities Work and Asset Management technical writers use RoboHelp to maintain the hyperlinked online Help topics supplied with the application. However, you can customize online Help without using an online Help authoring system.

Caution: Before modifying the content or navigation for the online Help, you should backup the online Help structure as it was delivered with the application. Also make sure that your customized structure is backed up before you install any system upgrades or patches. Only System Administrators and/or Database Administrators should have access to this functionality.

Customizing the Help Form

You can customize the “help map” to call your own customized online help documents for certain form / block combinations, while continuing to use the regular Oracle Utilities Work and Asset Management Help file for all other topics.

Please refer to the Customization guide for more information.

Installation Parameters Module

The installation parameters module tracks applied installations for auditing purposes. It also allows administrators to define system wide settings that apply to all user and all plants.

Parameter Descriptions

BATCH JOB DEBUG MODE

ON/OFF

This parameter determines whether the dbms_activity will be appended to the messages in the Job Manager Log. The dbms_activity will not be appended if the value is set to OFF. A value of ON will do otherwise.

CHART THUMBNAIL GENERATION

ON/OFF

Allows administrators to enable or disable the display of chart thumbnails. Disabling this feature can save system resources to speed up processing. Set to ON to display thumbnails and OFF to not display thumbnails. The default setting is ON. The SIA Application Server must be restarted whenever this parameter is modified.

CHART THUMBNAIL PROCESSING

ON/OFF

This Installation Parameter is used to manage the thumbnail processing in the on-line application. This controls whether chart thumbnails are displayed on metrics pages or in the charts views.

This parameter works in conjunction with the BATCH JOB MANAGER business rule which contains a batch job to regenerate the chart thumbnails on a regular basis. This batch job is called "GENERATE ALL CHART IMAGES" and should be disabled if you choose to turn this parameter OFF.

CHART_INVENTORY_VALUATION

Ex. ALL STOREROOMS

This value is used to restrict returned records for Inventory Valuation chart. Set the key value to a specific storeroom code to restrict chart by that specific storeroom, or leave value as 'ALL STOREROOMS' to retrieve data for all storerooms.

ENABLE PASSWORD RESET

ON/OFF

When set to ON the "Forgot Password" link is present on the login screen and users can click this link to have a temporary password emailed to the e-mail address in their user profile.

Database User

For security purposes, a special database user is required to assign temporary passwords. This database user must have roles limited to "CREATE SESSION" and "ALTER USER". This database user is not created during installation by default. Instead the script named createPasswordResetUser.sql, can be run manually after installation to create the database user. When the script is run, the installer will prompt for the username and password for the database user ALTER USER role.

OC4J Datasource

An OC4J datasource should be created using the same credentials defined in response to the createPasswordResetUser.sql script prompts. The name of the datasource should be "alterrole" + datasource," with datasource set as the name of the main datasource for the application. Adding the main datasource name creates uniqueness when multiple datasources exist for different environments on the same host machine.

INDEX_INITIAL_EXTENT

Ex. 20K

INDEX_NEXT_EXTENT

Ex. 20K

INDEX_TABLE_SPACE

Ex. INDX

JUMBO_SIZE_INITIAL_EXTENT

Ex. 40K

JUMBO_SIZE_NEXT_EXTENT

Ex. 40K

LARGE_SIZE_INITIAL_EXTENT

Ex. 30K

LARGE_SIZE_NEXT_EXTENT

Ex. 30K

LICENSE_OWNER

Ex. SYNERGYS

MID_SIZE_INITIAL_EXTENT

Ex. 20k

MID_SIZE_NEXT_EXTENT

Ex. 20K

PHONE_NUMBER_FORMAT

Ex. (XXX) XXX-XXXX

This is the phone number format used by the SIA application. Example: a raw value of 9259357670 with a format mask of XXX-XXX-XXXX would result in a displayable phone number of 925-935-7670.

For non-english installations, the code should be set to NO FORMAT.

PK_INITIAL_EXTENT

Ex. 20k

PK_NEXT_EXTENT

Ex. 20k

PK_TABLESPACE

Ex. INDX

PRIMAVERA

Ex. s1876s1554

SCHEDULING_TOTAL_EST_HRS_DISP

ON/OFF

If set to ON, will display Total Hours Scheduled and Labor Estimate for each craft within the Daily and Workweek Scheduling modules. This also controls whether the Autofill Estimates tool is available in these modules.

SIA_TABLEOWNER

Ex. XADMIN_SYNERGEN

SMALL_SIZE_INITIAL_EXTENT

Ex. 20K

SMALL_SIZE_NEXT_EXTENT

Ex. 20K

SPELL CHECK

ON/OFF

This option controls the Spell Checking feature.

SUPER_USER_ROLE

Ex. SUPER

TABLEOWNER

Ex. SYNERGEN

TABLESPACE_NAME

Ex. USERS

TEMPORARY_TABLESPACE_NAME

Ex. TEMP

TINY_SIZE_INITIAL_EXTENT

Ex. 20K

TINY_SIZE_NEXT_EXTENT

Ex. 20K

Objects beginning with SDBT

ON/OFF

Most of these objects trigger a transaction to populate a log, although some trigger other events. The value controls whether the trigger is enabled or disabled.

Objects beginning with SAUT

ON/OFF

These objects control whether or not the indicated module is tracked in the system audit log module. The value controls whether the trigger is enabled or disabled.

Objects beginning with SABI

ON/OFF

These objects control Business Intelligence (BI) Integration triggers. The value controls whether the trigger is enabled or disabled.

Modules Administration - Forms Module

Use this module to access and maintain specific form information and processing. This includes defining which fields in a module are required entry, which are required at a certain point in time, setting up defaults, and more.

Required Fields, Enter Data, Secondary Required Fields, and Status Required fields

These three Views allow you to set requirements and/or defaults for fields in designated modules. Since fields are located within blocks on a form, you must enter both the Form Name and the Block Name for each field. The system then presents a List of Values based on the possible fields in that form and block.

You can list User Defined fields in the Module Administration - Forms module but you must use the name for the field (Attribute 1, Attribute 2, etc.) rather than the display label you assign to the field.

REQUIRED FIELDS - Fields on any given form can be marked as required entry, forcing users to enter a value into the field before saving the record. Within Required Fields, the Form Name and Description are displayed.

ENTER DATA - Enter Default values for fields.

SECONDARY REQUIRED FIELDS - Designate fields as required based on whether or not another field has been populated.

STATUS REQUIRED FIELDS - Designate fields as required based on the status of the record.

Field Localization View

The Field Localization view allows you to customize labels for the fields on a form.

Field Localization settings are dependant on the Plant where they were configured. For example, a user can view all localized fields for Plant 01, but if he or she logs on to Plant 02 where no customized field labels are set, only system labels will be available. This rule is true for most customized settings.

Please refer to the topic on [Localization](#) for complete information on how to configure localization settings.

Module Reports

Enter Report IDs in this view to create a quick link on the actions list of the module to that report. The system brings over the Report Title from the report description based on the Report ID. The Action Text field defines how the link will appear on the Actions list.

Select the Default box to indicate the report that should be printed as default when more than one report is configured in the module and there are options to Print <report> with Attachments.

The list of values for the Report ID is limited to reports that the user has access to through responsibilities. Users attempting to access the report must also have the report in their responsibilities, and they must have access to the all_cons_columns view. This view access is granted though sql using the command:

```
Grant select on all_cons_columns to SUPERUSER;
```

Copy Record View

Copy Record configuration should only be completed by a qualified database administrator with solid knowledge of the database structure.

Use the Copy Record view in Modules Administration - Forms to indicate the tables (views) that should be copied when the Copy Record action is selected from within a module. Here you enter or exclude all of the views in the module that you want to copy and indicate the execution order. Only the tables indicated in this view will be copied with a record. Some forms are delivered with default table and field values. These can be used as a guideline for configuring other forms.

Execution order is extremely important when configuring Copy Record functionality. The system must be configured to copy the header record first, then the child records, then the children to any of those child records, and so on. For example, the Asset module includes multi levels of views. If, for instance, SA_ASSET_PERMIT were placed ahead of SA_ASSET in the copy order, the system would not recognize SA_ASSET_PERMIT as having any valid data because the information needed from SA_ASSET would not yet be available. Likewise, SA_ASSET_PERMIT_ATTACHMENT could not be ahead of SA_ASSET_PERMIT for the same reason. Ordering the tables in a module in the wrong way could result in error messages or the creation of corrupt data.

To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Users must also have access to the all_cons_columns view to use this functionality. This view access is granted through sql using the command:

```
Grant select on all_cons_columns to SUPERUSER;
```

Field Defaults

Entries are ONLY made in the Field Defaults view if a change needs to be made to the field when the record is copied. If a table is included in the Copy Record view, but no fields on that table are indicated in the Field Defaults view, all of the fields will be copied with no changes made to the data. Fields included in the Field Defaults view will either be cleared of existing data when copied (when the Default Value is left blank) or to indicate a Default Value (enter the value in the Default Values field). The lists of values in both views are validated for tables in the module, and fields in the tables.

Copying Status Fields

Default values become very critical in cases where the record being copied includes a status field. In most cases, you would want to set a Default Value for the status field on all copied records so that the new record cannot be created in an unusable status. Copying a status incorrectly could result in error messages or the creation of corrupt data.

Responsibilities

Once a module is set up in the Copy Records view of the Module Administration (Forms) module, make sure that the users also have the Copy Record responsibility that is specific to the module.

Every module that includes the Copy Record functionality is listed as [FORMNAME] - COPY RECORD when you select Copy Records as from the Type drop-down in the Responsibility module.

Sequence Numbers

When the action is selected from a module the system opens a wizard that walks users through the process of creating the new record. If record numbers for the module are set to be auto-generated, the system creates the number as it would when any new record is created. Otherwise the user is prompted to enter the record number and any other required information.

Once a module is set up in the Copy Records view of the Module Administration (Forms) module, make sure that the users also have the Copy Record responsibility that is specific to the module. After these settings are complete, users with the responsibility can use the Copy Record action for the module that was configured.

Database Tables

When records are copied, the system creates temporary tables. When the copying process is complete, the system discards this data in the database recycle bin. To prevent data accumulation on the database, DBAs should clean out the database recycle bin periodically.

Special LOVs View

Construct Custom List of Values queries in the Special Lists of Values view. Enter a List of Values Name and Title, Group, and Record Group. At that point you can enter a detailed Description and write the actual SQL query which can be as simple or sophisticated as required.

Custom Menus View

Use this view to define up to 20 custom menu items for each module. The menu items that you create can open reports or custom API calls that you develop using SQL and SAPI Triggers. Once you complete the fields in this form, the system adds a menu item to the menu bar of the selected module. To users, the added menu items look like the standard options, but will add greater accessibility and functionality specific to your organization.

Please refer to the Customization Guide for a full list of SAPI Triggers and more information on Custom Menus.

Selection Order By View

The Selection Order By view allows you to determine the default Order By options on the Search Options page in a given module.

Form Name

Identifies the specific form where the Order By list will appear in Search Options.

Seq (sequence)

The items on the Order By list will be listed numerically according to this number. Search Results will be ordered by the first value on the list if no other selection is made. If you want to change the default value, change the sequence numbers to making the desired default first on the list.

Label

The text in this field shows how the items will appear on the list on the Search Options page.

Used

This field indicates which form fields should be used to sort the forms when they open.

Used (Check Box)

If this box is checked the field will be used on the Order By list. These check boxes are a convenient way to add and remove fields from the Order By list without having to physically enter and remove them from the Selection Order By Views list.

Block Name

Indicates the specific block where the fields on the Order By list can be found.

Sys

A check in this box indicates that the field is required by the system.

Duplicate View

The Duplicate view allows you to set up specific parameters for when you use the Duplicate function in a module. By setting this view correctly you can prevent unnecessary or incorrect information from being copied over when you duplicate a form.

Clear (check box)

If this check box is marked the system will clear this field when you use the duplicate function.

Invalid (check box)

If this check box is marked for a field, the system automatically marks the data in the field as invalid. When you save the record the system checks to see if it is actually invalid and then re-validates it or returns an error message if it is no longer valid. This function helps you to avoid duplicating inaccurate information.

Check (check box)

If this check box is marked for a field, the system verifies that the information to be copied is valid. For example, if you are copying a Blanket Contract and the Check check box is marked for the field Blanket Contract Number, the system will verify that the Blanket Contract number to be copied is still valid and used in the system before it uses it on the new form. This function helps you to avoid duplicating inaccurate information.

Replace with Value

In this field, you can enter the data that you would like to have entered in place of the data from the original form. You can not put in default values for system required fields.

Allow Duplicate View

The Allow Duplicate View allows you to set up blocks on a form that can be duplicated and validated. Select the block name and check the check boxes next to that block name depending on whether or not you want duplication to be allowed for that block and you want it to be validated immediately after it is duplicated.

Modules Administration - SIA

The Modules Administration - SIA module mirrors the functionality of the corresponding forms module, but for modules based on the Synergen Internet Architecture (SIA) rather than Oracle forms. Using the Modules Administration - SIA module, you can define required or secondary required fields and setup default values that the system will automatically insert into new records.

You can search the SIA Modules Administration module using field names or field sources. The field source is the page or view where the field is found. If you don't know a specific field name or field source, you can find out by right clicking any field in an SIA module to see the field name, field label, and field source information.

The Results window opens listing all records that meet your search criteria. If you search without entering specific information, the Results window opens listing all records.

Fields

Field Source and Field Name

Field Source identifies page or view where the field is located. Field name identifies the name of the field on the source.

Default Value

If you enter a Default Value the system will automatically insert the specified value into the field when a new record is created. Users can overwrite default values if necessary.

System

When the System box is checked, the system requires the field be populated before the record can be saved. When the System box is checked, the Required box is automatically checked as well and you cannot modify either setting.

Required

Check the Required box if you want to make the field a required field. If you set a field as required, users must enter a value into the field before the system will allow them to save the record.

Secondary Fields View

Click the Secondary Required link to designate a second field to be a required field when the current field is populated. If secondary field information has been entered, the Secondary Fields Data page opens showing that information. If secondary field information has not been entered, click the New icon to open an empty data page.

Enter the Second Field Name and mark the Required check box. Check the Required box to make the field a required field.

Enter a Field Value to indicate that the second field is required only when the first field contains the specific value shown. Leave the Field Value blank if the second field is always required so long as the first field is populated with any value.

Charts and Metrics

Responsibilities

Use the Responsibilities module to add the Charts and Metrics that you want users to have access to. Charts are displayed in the home page and in the Charts module. Metrics are displayed in the home page and the Filtered Metrics module.

Filtered Metrics

While a Metric represents a single queried or calculated value, a Filtered Metric further defines that value. With a Filtered Metric, the data used to calculate the metric value is filtered by specific values. Once granted access, users can see Filtered Metrics on their home page and in the Filtered Metrics module. Metrics and Filtered Metrics are managed within the Metrics Administration module. An administrator can create both Metrics and Filtered Metrics before granting access to each Filtered Metric to specific Responsibilities. Access to the Metrics Administration module must also be granted through the Responsibility module.

Charts

The following types of charts can be added to the system and accessed from the Chart list or Home Page:

- Charts based on Pivot Lists
- Charts based on spreadsheet data, that do not query the Oracle Utilities Work and Asset Management database
- Spreadsheet data with no charts

See the [Charts Administration](#) User Guide for information on adding these charts.

Maximum Chart Records

Modify the `max_chart_records` property in the `config.properties` file to limit the number of records to use when querying data for the charts (interactive, detailed charts and generation of thumbnail images). If the number of records retrieved is too large, the system may error before displaying the chart. This is because there may not be enough memory or resources on the application server to handle the data. There is no recommended value for this setting because it will depend on the environment. If a value is not specified, the default value will be 20,000 records. If the number of records continues to be a problem, the underlying views that provide the data should be modified to include additional filters to limit the data.

You can find the `config.properties` file located here:

```
\ora10gMID\j2ee\OC4J_INSTANCE\applications\INSTANCESynergen\INSTANC  
Esynergen\config directory
```

where "INSTANCE" is the name of the OC4J instance entered by the installer.

The property is called "max_chart_records" in that file.

Charts Home Directory

IIS is used to generate thumbnail images representing the charts at specific points in time. The reason why thumbnail images are used instead of the actual chart is to reduce the time it takes the home page to display. By using thumbnail images instead of the actual charts, we reduce the number of queries performed before the home page is displayed.

To generate the charts, the IIS website should use the following Oracle Utilities Work and Asset Management directory as the "home directory". This directory contains the necessary programs to generate thumbnails:

The Charts IIS Server home directory must point to

\ora10gMID\j2ee\OC4J_INSTANCE\applications\INSTANCEsynergen\INSTANC
Esynergen\charts directory

where "INSTANCE" is the name of the OC4J instance entered by the installer.

The permissions for synergen\charts\data should be set so that all users have write permissions.

1. **On the Application Server, select Start>Programs>Administrative Tools>Internet Information Services (IIS) Manager.**
2. **Navigate to and expand the Web Sites folder.**
3. **Right click the web site defined for the Synergen 6 Chart Service and select Properties.**
4. **Select the Home Directory tab.**
5. **For the Local Path, browse to and select the charts folder.**
6. **Click the OK button.**
7. **Click the Apply button.**
8. **Click the OK button.**

Notes on Charts in Office 2007

The chart functionality in Oracle Utilities Work and Asset Management used the Microsoft Office Excel PivotList and Chart features to display interactive charts. These features were based on the Office Web Components (OWC) that were a part of Office XP and 2003 versions. The current version Microsoft Office, 2007, no longer includes this feature. To continue to use this functionality, customers must use older versions of the Office Web Components as described below:

1. To register a new chart with the application the client machine that creates the chart HTML file must be using either Office XP or Office 2003. These are the only versions of Microsoft Office that publish PivotTable and PivotChart HTML files.
2. To view interactive charts within the application, the client machine must have the XP version of Office Web Component installed. This is an ActiveX control that can be installed in conjunction with Office 2003 or 2007). The OWC ActiveX controls are available at these Microsoft pages:

Office 2003 Web Components Download:

<http://www.microsoft.com/downloads/details.aspx?FamilyID=7287252c-402e-4f72-97a5-e0fd290d4b76&DisplayLang=en>

Office XP Web Components Download:

<http://www.microsoft.com/downloads/details.aspx?FamilyID=982b0359-0a86-4fb2-a7ee-5f3a499515dd&DisplayLang=en>

3. The IIS ASP server that generates supporting Chart Thumbnails must have the Office XP OWC ActiveX control described above.

Description of Missing Features in Office 2007

When installing Office 2007 why are the Office Web Components removed from my system?

Other than in Project Server, the Microsoft Office Web Components will no longer be shipping in Microsoft Office. Because of this change the components are removed from

your system during the installation of Office 2007 if they were installed by a previous version of Microsoft Office. Users who need the Office Web Components can download and install them online from the Microsoft Download Center.

HTML is no longer a supported Excel publishing format.

Previous versions of Excel allowed for publishing of Excel files to HTML with interactivity using the Microsoft Office Web Components. With the introduction of Excel Services, Microsoft has shifted focus to services instead of HTML. As part of this focus, Microsoft has removed support for saving HTML files with interactivity using the Office Web Components.

More information

<http://office.microsoft.com/en-us/products/FX101633871033.aspx>

Batch Processes

Generate All Chart Images

sdbp_generate_all_chart_images (job_in, plant_in); - Generates chart images used on home page. Run Now is not an option on the Actions list for this batch process. If you want to regenerate the thumbnail chart image on the spot, open the Charts Administration module, locate the chart on the list, and click the Regenerate Image button.

Generate Charts

sdbp_generate_chart_image (job_in, chart_id_in, plant_in) - Generates specific chart images. For the chart identifier, this procedure uses only the number following “s_chn” in the chart name (for example, 140 is the chart_id for chart s_chn140). Run Now is not an option on the Actions list for this batch process. If you want to regenerate the thumbnail chart image on the spot, open the Charts Administration module, locate the chart on the list, and click the Regenerate Image button.

Generate Metrics

sdbp_metric_handler (job_in, plant_in); - Processes all metrics to get current data.

Business Rules

Charts and Metrics Settings Rule

CHART or METRIC NAME	Criteria 1	Criteria 2	Criteria 3	Criteria 4
INVENTORY TURNS	2	YEAR(s)		
PM FORECAST MONTHS	7	YEAR(s)		
PM FORECAST MONTHS - EST DUR	5	YEAR(s)		
PM FORECAST WEEKS	5	YEAR(s)		
PM FORECAST WEEKS - EST DUR	5	YEAR(s)		
PM HISTORY MONTHS	2	YEAR(s)		
PM HISTORY WEEKS	2	YEAR(s)		
PROJECT ANALYSIS	1	YEAR(s)		
W/O ACTUAL COST TO PLANNING EST	2	QUARTERLY		
W/O PLANNING ACCURACY INDEX	3	MONTHLY	22	

Description
Criteria 2: Time Unit

This rule is used to control the amount of data retrieved by charts to help prevent overloading the systems with memory issues. For each chart or metric, all plants must have identical settings.

Chart or Metric Name

The name for the chart or metric.

Criteria

CRITERIA 1 sets the number of complete prior time units (Months, Quarters or Years) that will be retrieved. Current partial data is included.

CRITERIA 2 sets the type of time units to retrieve (Months, Quarters or Years).

CRITERIA 1 and **CRITERIA 2** must be used together to determine the overall time-frame for data retrieval. For example, if you want to retrieve the current partial data plus the data for 4 prior months, enter '4' for Criteria 1 and 'Monthly' for Criteria 2. Even if the chart does not physically show months quarters or years, Criteria 2 must be set to indicate the type of time unit to retrieve.

For each chart or metric, all plants must have identical settings. If multiple settings are set for different plants - the minimum value will be used. The maximum time period for which data can be retrieved is 5 years.

CRITERIA 3 - 7 may define additional settings for the chart or metric. Refer to the description for more information.

Installation Parameters

CHART_INVENTORY_VALUATION

Ex. ALL STOREROOMS

This value is used to restrict returned records for Inventory Valuation chart. Set the key value to a specific storeroom code to restrict chart by that specific storeroom, or leave value as 'ALL STOREROOMS' to retrieve data for all storerooms.

CHART THUMBNAIL GENERATION

ON/OFF

Allows administrators to enable or disable the display of chart thumbnails. Disabling this feature can save system resources to speed up processing. Set to ON to display thumbnails and OFF to not display thumbnails. The default setting is ON. The SIA Application Server must be restarted whenever this parameter is modified.

CHART THUMBNAIL PROCESSING

ON/OFF

This Installation Parameter is used to manage the thumbnail processing in the on-line application. This controls whether chart thumbnails are displayed on metrics pages or in the charts views.

This parameter works in conjunction with the BATCH JOB MANAGER business rule which contains a batch job to regenerate the chart thumbnails on a regular basis. This batch job is called "GENERATE ALL CHART IMAGES" and should be disabled if you choose to turn this parameter OFF.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Display Trusted Sites Link

Displays the link: "Add Chart Server as a Trusted Site" to the Charts List page (not the Chart Admin page) giving the user the option to add the current server to the list of trusted sites.

Report Administration Module

The Report Administration module is used to access and run existing reports as well as to add custom reports. In order to run, each report must have a Report Administration record with a unique Report ID. The Report Administration record includes fields to describe and classify the report and locate the report's executable files.

Reports are called from Oracle Utilities Work and Asset Management using either Oracle Reports Engine or the BI Publisher Reports server.

Please refer to the Custom Reports section in the Customization Guide for information on creating custom reports.

Business Rules

Web Configuration Rule

Rule	Option	Setting
REPORTS ALWAYS PREVIEW	YES	
REPORTS CUSTOM VIRT DIRECTORY		http://spl-rome.us.ors
REPORTS DEFAULT OUTPUT FORMAT		PDF
REPORTS OUTPUT PHYS DIRECTORY		D:\ora10gmid\Apache
REPORTS OUTPUT VIRT DIRECTORY		http://spl-rome.us.ors
REPORTS SERVER NAME		repQA1715XAS

Define web configuration settings.

Rule, Option, and Setting

Enter YES or NO in the Option column for each of the rule keys. Also enter the file path or format (as appropriate) in the Setting column.

BI PUBLISHER MAX RUNTIME - This value determines the maximum number of milliseconds that they system will wait before timing out on accessing the BI Publisher Report.

BI PUBLISHER SHARED FOLDER - This indicates the folder in BI Publisher that contains all of the WAM reports.

REPORTS ALWAYS PREVIEW - Setting this option YES forces all printing to be previewed first. Reports are converted to a .pdf file and opened in Adobe acrobat.

REPORTS BARCODE FONT - Enter a value in the setting field to specify the font to be used on reports that include a barcode field. The font that is entered should be available in your system fonts. You can find fonts by searching the internet for "Free Barcode Fonts."

REPORTS CUSTOM VIRT DIRECTORY - This is the web server virtual directory to run the Oracle Reports CGI program for the web version.

REPORTS DEFAULT OUTPUT FORMAT - Select the default format for all reports. Settings include TXT, PDF, RTF and EXCEL (BI Publisher ONLY).

REPORTS OUTPUT PHYS DIRECTORY - This is the web server physical directory to put report output for the web version. To enable e-mailing of Purchase Orders to Vendors, allow network access to the directory defined under this rule key. Once this access is allowed, identify this network share in the E-Mail Configuration Business Rule under the key PO EMAIL FILE LOCATION.

REPORTS OUTPUT VIRT DIRECTORY - This is the web server virtual directory to retrieve report output for the web version.

REPORTS SERVER NAME - This is the name of the reports server for the web version.

UPLOAD DIRECTORY - This is the directory where files are stored when they are uploaded to support receiving multiple trackable stock items.

Responsibility Module

Users cannot see or do anything in the system - aside from working in the home page - unless they have at least one Responsibility. Responsibilities determine the standard Oracle Display, Select, Insert, Update and Delete privileges described in the security matrix. They also determine which parts of the system are available to users all the way down to the level of specific fields.

There are several Responsibility Types. Under each type, individual items control objects that fall into these categories.

As a default all of the objects are prohibited to a user unless there are specifically allowed to the user by a responsibility. Responsibilities are assigned to users in their user profiles.

Responsibilities cannot be extended to custom programs accessed through the In House menu in the Administration subsystem.

Responsibility Types

CHARTS TYPE - Controls the charts that are available to the user.

COPY RECORDS TYPE - Controls which modules include the Copy Record action on the Actions list. Modules must also be configured for copying in the Copy Record view of the Module Administration (Forms) module. In order for the Copy Record action to appear on the Actions list in any module you must have BOTH the Responsibility and at least one table added to the Copy Record view of the Module Administration - Forms module.

CUSTOM MENUS TYPE - Controls which custom menus the user can see throughout the system. Most modules have a custom menu function that can be turned on or off when you create custom menus in that module. In general, the naming structure for these Functions is “[module name] - Custom Menu”.

FILTERED METRICS TYPE - Controls the filtered metrics that are available to the user .

FUNCTION TYPE - Controls access to views, actions, wizards, and other task based parts of the system.

MODULE TYPE - Controls which modules the user can view.

REPORTS TYPE - Controls which reports users can view or print.

Furthermore, by checking the Display, Select, Insert, Update, and Delete check boxes, you can determine whether or not users with the given responsibility have the power to perform any one of these tasks on any one of the items, where applicable.

The nature and structure of your organization will determine how you use responsibilities. Beyond a few generic delivered responsibilities, each organization establishes its own responsibilities to meet its unique needs. Responsibilities can be based on specific tasks or job titles and they can be layered. The strategy that your organization uses will be determined by such considerations as business practices, managerial and supervisory responsibilities, level of effort to set up and maintain the system, personnel turn-over, etc.

EXAMPLE:

A sample responsibility structure might have 3 levels. ADMIN, LEVEL1, and LEVEL2.

You would assign the ADMIN responsibility to any users that you want to have complete power over the system. You would then include every Module, Function, and Report in that Responsibility, and check all of the boxes under Display, Select, Insert, Update, and Delete. Users granted this Responsibility would then have complete access to everything in the system.

You would assign the LEVEL1 Responsibility to users with moderate access to the system. These users may have access to all Modules and Reports, but you may choose to limit the types of functions available to these users or prevent them from deleting certain objects by leaving the Delete check boxes unchecked.

The LEVEL2 Responsibility might be assigned to users with very limited access to the system. You might even have a LEVEL2-Work and a LEVEL2-Purch and only assign modules and functions that pertain to very specific job functions to these Responsibilities.

As you can see, the Responsibility module affords tremendous flexibility and control over the system. You should work closely with your Oracle Utilities Work and Asset Management representative to develop your Responsibility matrix so that it works to the maximum benefit of your organization.


Copy Record

RESPONBL - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Application Security

The Application Security module works with the Responsibility module to control the allowed privileges to specific objects in the system. Only modules that are launched within Internet Explorer are controlled by settings in the Application Security module. Modules that are accessed in Oracle Forms are controlled by the Responsibility module.



Once you create a responsibility name, enter a description and save, you can click the Add Modules icon to build the ability list. When you select this icon, the system allows you to filter the list of modules by subsystem and/or module.

Place a check in the box next to each ability that is available to the responsibility. Place a check in the Allow Insert, Allow Update, or Allow Delete columns, based on which of these activities you want to permit for the responsibility. It is assumed that any abilities for the module that are left unchecked are not available to the responsibility. If you do not want users to have access to the module at all, do not include that module in the abilities list. This means that the module will not appear in the Application Map lists or on any menus.

Once modules are added to the active ability list you can click the Pages link to control which pages in each module the user with this responsibility has access to. If no pages are configured, the system defaults to have all available pages accessible to the responsibility.

Place a check in the box next to each ability that is available to the responsibility. If only the Available check box is selected, users have the insert, update, and delete abilities. If a

check is placed in the Allow Insert, Allow Update, or Allow Delete columns, it is assumed that any abilities for the page that are left unchecked are not available to the responsibility.

The fields screen works in the exact same way as the Pages screen.

Select Assigned Users from the Views list to assign a responsibility to several users. The alternative is to assign responsibilities by selecting Responsibility from the Views list in the User Profile module and adding them on a user by user basis.

Sequence Numbers Module

Throughout the system many numbers - such as ID Numbers - must be unique because they identify their record. The system always verifies that these record identifying numbers are unique, however, you can also set the system to generate the numbers to save users from taking the time to create unique numbers. Using the Sequence Numbers module you can control the format of sequence numbers as well as whether the number will be provided by the system.

If a module is not specifically referenced in the Sequence Numbers module, the default is to have the record identification number for that module created by the user.

When you adjust the settings in this module the changes only apply to the Plant that you are logged on to.

Fields

Table Name

The Table Name indicates the table that contains the number and is entered and maintained by Oracle Utilities Work and Asset Management.

Sequence Number

If the system generates the number, you can determine if there is a starting number, as well as what that number is to be. For example, entering 100 would cause the system to begin using the number 100, then 101, 102, etc.

Prefix

If the system generates the number, you can determine the prefix that it will use. If you enter "YY" the system will use the current year. Any other letters or numbers entered will be represented as their value. For example, entering "B" would cause generated numbers to begin with "B".

If at some point you would like to change or omit the prefix, you can do so by entering a new prefix or deleting the existing prefix. Make sure that the new value has not already been used or else you will create duplicate numbers and the system will generate an error.

Length

The length indicates the maximum number of characters that can be used in the number. The length indicates the size of the number that can be used in the table, not necessarily what the field will show on screen.

System

A check in the System check box indicates that the sequence number should be system generated. Uncheck the box to allow users to create the number.

User Profile Module

In User Profile you can set up and maintain profile information specific to each user. Each time a user signs on to the application, the system checks this module for default information such as which printer location to use as a default, which Plant Code to use as a default, and other information that is used throughout the system.

Each username granted access to the application must have a User Profile record to use the system. Usernames and Employee Numbers entered in the User Profile must be unique for each user. No duplicates are allowed. The Employee Number returns information from the Employee module (Resource subsystem). Default Information consists of a Name used to print on documents and reports, Printer (of choice), and Plant Code (used when signing on to the system).

Administrator Access to User Profile Records

Access to all User Profile records is controlled with password authority. Only users granted authority can access all User Profile records, otherwise users may only access their own User Profile (based on username)

Administrator access to user profile information, enrolling users, and changing user passwords can be summed up with the following:

- User Profile “administrators” are indicated by assignment of the USER PROFILE ADMINISTRATOR responsibility function.
Having this responsibility function allows a user to see User Profile records other than their own and to have the ability to insert, update, or delete user profile information.
- Altering of passwords requires ALTER USER database privileges in addition to the USER PROFILE ADMINISTRATOR responsibility function.
Having this database privilege allows administrators to access the change password features.
- The security function, USER PROFILE ADMINISTRATOR, and four database privileges are required to use the User Enrollment Wizard to create database users:

Database Privileges

- CREATE USER
- GRANT ANY ROLE
- CREATE TABLE
- SELECT ANY TABLE

Users with these database privileges will see the database admin page in the Enrollment Wizard when creating users.

Selecting the User Enrollment action from the User Profile module launches the User Enrollment wizard.

Note: Administrators may want to disable the Insert, Update and Delete abilities for most blocks in the User Profile module for most modules. In particular, the Responsibilities view should be disabled to prevent users from adding responsibilities from within their own User Profile record. If you choose to turn off these abilities for all blocks in user profile, make sure that they are at least enabled for the Change Password block.

Configuration Scenarios

The following scenarios describe how the system might be configured to achieve different levels of access to user profiles and responsibilities.

Scenario 1: User with no USER PROFILE ADMINISTRATOR function

1. **User queries User Profile module.**
2. **User navigates to Responsibility view or FGA Responsibility view and attempts to insert, update, or delete.**

Result: Error message stating no access to do this action.

Scenario 2: User with USER PROFILE ADMINISTRATOR function but no access to Responsibility module

If

- User POWER is granted with USER PROFILE ADMINISTRATOR security function but no access to Responsibility module.
- User POWER has 3 Responsibilities granted (RESP1, RESP2, and RESP3).
- User END has 2 Responsibilities granted (RESP1 and RESP4).

then

- User POWER cannot affect responsibilities of user END'S account.

User with USER PROFILE ADMINISTRATOR function and has access to Responsibility module

If

- User POWER is granted with USER PROFILE ADMINISTRATOR security function and has access to insert, update and delete in the Responsibility module.
- User POWER has 3 Responsibilities granted (RESP1, RESP2, and RESP3).
- User END has 2 Responsibilities granted (RESP1 and RESP4).

then

- User POWER can grant RESP2 and RESP3 to user END.
- User POWER can update or delete RESP1 on user END's account
- User POWER can affect RESP4 on user END'S account.

Business Rules

Password Security Rule

The screenshot shows a configuration window titled "Business Rule PASSWORD SECURITY". It includes fields for Rule ID (PASSWORD SECURITY), Configuration, Parameter, and a Limit? checkbox. The Description field contains: "This rule utilizes the data stored in the User Profile to notify users upon logon to the the current password has expired and prompts for a new password." The Comment field contains: "Use to turn 'on' or 'off' password expiration checks upon logon to Synergen Series." Below these is a table for Rule Enforcement and Option Status:

Rule Enforcement	Option Status
CHECK EXPIRATION	ON
MINIMUM PASSWORD LENGTH	4
PASSWORD DURATION	30

At the bottom, there is a Description field.

Utilizes the data stored in the User Profile to notify users upon logon to the system, the current password has expired. It also prompts for a new password.

Use to turn on or off password expiration checks upon logon to the system.

Rule Enforcement and Option Status

ADMIN EMAIL- This is the contact e-mail that will be included in the email sent when users reset their password.

CHECK EXPIRATION - When this is ON, users' passwords are checked against the EXPIRATION_DATE stored in SA_USER_PROFILE. If the password has expired the system prompts for the creation of a new password. If the OPTION STATUS value for this rule key is set to OFF, the system will not check the expiration date and will not prompt for a new password once the current password expires.

MINIMUM PASSWORD LENGTH- Default is 8. A value must be entered in this field if you have [password reset](#) enabled.

PASSWORD DURATION - This value determines the number of days that the password is valid. If the CHECK EXPIRATION rule key is set to YES, the system prompts the user to create a new password on the expiration date indicated in the Password Administration view of the User Profile module. When the password is reset, the system sets the expiration date ahead to the number of days entered in this rule key. For example, if the Password Duration is 30 and you change your password on May 1, the system sets the new Expiration Date to May 31.

Printer Alias Rule

Business Rule PRINTER ALIAS

Rule ID: PRINTER ALIAS Configuration List Limit?

Desc: This rule lists the printer names and destination names to be used to print within the Synergen Series.

Comment: The "printer alias", as defined in the "NAME" column, will populate the Printer field on the user's User Profile record as default information. This printer will override the user's PC default printer.

Name	Actual Name	Short Desc.
1000HP8000N	WUSA1000HP8000N	
685HP8KN ON TOPAZ	WTOPAZ685hp8KN	
850HP8KN ON TOPAZ	WTOPAZ685hp8150N	
CLOSEST	WTOPAZ800hp5si	
FRIENDLY NAME	Technical Name	
MAIN PRINTER	Wusa1000HP8150MF	

Description

Indicate the printer names and destination names to be used to print within the system. The printer alias, as defined in the NAME column, will populate the Printer field on the user's User Profile record as default information. This printer will override the user's PC default printer.

NAME - The name field establishes an "alias," or user-friendly name for the printer indicated in the Actual Name column. This value will populate the Printer field on the User Profile record as the default (up to 30 characters).

ACTUAL NAME - Enter into the "ACTUAL NAME" column the printer name that a specific operating system would recognize (up to 30 characters).

If you have many different operating systems (i.e. Windows95, WindowsNT, etc.) printing to one printer, the printer name is stored in the "ACTUAL NAME" column. This printer name can be found in the Control Panel for the operating system under Printers.

You must enter the printer name in the following format: \\<server name>\<actual printer name> (e.g. \\MYSERVER\685HP8KN if "685HP8KN" is the actual printer name), OTHERWISE THE PRINTER WILL NOT BE RECOGNIZED. If the printer name changes, you only need to change the Business Rule setting, not all of the User Profile records.

SHORT DESC. - Enter into the "SHORT DESC." column a description of the printer (up to 30 characters).

GS DEVICE - If the PRINT ATTACHMENTS TO PRINTER rule key in the ATTACHMENT PRINT CONFIGURATION Business Rule is set to ON, enter into the "GS Device" column the Ghostscript device name that applies to the printer. An example of this would be "LaserJet" for an HP LaserJet printer. To find a valid list of printer device names, please refer to your Ghostscript documentation.

Batch Processes

Synchronize User - sdbp_clean_user_n_user_profile;

Synchronizes records in SA_USER and SA_USER_PROFILE by inserting missing user records for matching user profiles, setting a default plant if not specified, and deleting user records without matching user profiles.

Copy Record

USERPROF - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

When the Copy Record action is selected from the Actions list in the User Profile module, the system opens a wizard that walks you through the process of copying a user profile. The first screen of the wizard asks for the username and includes three check boxes which represent the three business rule authorities that might be associated with the user profile (Timekeeping Authority, Procedures Authority, Work Request Authority) with the applicable authorities checked. The user can use this value or choose un check the boxes to exclude the authority from the new profile. The screens that follow depend upon the boxes that are checked here. If a box is not checked the corresponding screen to configure the authority is not displayed. Follow the screens in the wizard to copy the user profile record. Additional adjustments can be made on the resulting record when the wizard is complete.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

User Profile Administrator

Allows users the ability to select, insert or update user profile records.

Activate Pins

Grants the administrative ability to activate locked PIN numbers in the User Profile module. A PIN becomes locked after a determined number of unsuccessful attempts to enter a PIN number.

User-Defined Fields Module

Define user defined fields for modules where they are needed.

Use of this module requires technical understanding of the database. Only your Database Administrator (DBA) or technical level users will be able to create User Defined Fields. However, this discussion is presented for anyone who may deal with planning and implementing User Defined Fields.

At it's simplest, a User Defined Field can be a basic information holder containing numeric or alphanumeric information that does not interact with the rest of the system. At a more complex level, information from a User Defined Field on one record type can be copied to another record type – for example, a routing number on a Requisition that is passed on to the Purchase Order. User Defined Fields can also be used for customizing reports.

Please refer to the user guide topic on User-Defined fields for more detailed information on setting up these fields.

User-Defined Fields on Related Tables

When a UDF is defined for a table that has a related table, the same UDF definition needs to be applied for the related table. For example, if ATTRIBUTE3 at SA_WORK_ORDER_TASK is redefined with NUMBER datatype and length 8, ATTRIBUTE3 at SA_WORK_HISTORY_TASK should also be redefined as NUMBER datatype, length 8.


The following shows a list of tables that have related tables and have UDFs:

- SA_WORK_ORDER <=> SA_WORK_HISTORY
- SA_WORK_ORDER_MATERIAL <=> SA_WORK_HISTORY_MATERIAL
- SA_WORK_ORDER_PERMIT <=> SA_WORK_HISTORY_PERMIT
- SA_WORK_ORDER_TASK <=> SA_WORK_HISTORY_TASK
- SA_PURCHASE_ORDER <=> SA_DELIVERY
- SA_PURCHASE_ORDER_ITEM <=> SA_DELIVERY_PO_ITEM
- SA_WORK_ORDER_PERMIT <=> SA_WORK_DESIGN_PERMIT

UDF Setup Window

The User Defined Fields Setup window determines the table assignment, basic appearance and validation (checking against a list of values) of the fields. Once you have created a new record here, you can use the Setup Table Definition view to further define how the new User Defined Field will function.

The window includes a field for the affected table name and ten line items for the ten available Attribute fields.



UDF Setup Window

Table Definition

Once you have created a User Defined Fields Setup record to indicate that a window (i.e. table) should display User Defined Fields, and have defined the basic characteristics for the User Defined Fields, you can use the Setup Table Definition view to make sure that the database has been prepared to accommodate the new or modified fields. These options define the data characteristics of the fields and how they behave within the database structures and processing.

The window includes fields to make these refinements as well as a display that confirms your selections. Since these selections change the actual structure of the table and the data it allows, the window provides a set of check boxes and a button to control when and how the updates are made.




Table Definition view

Determining Which Windows Show UDFs

You must know the name of the table (rather than the window name) that will include the UDF.

To Determine which Tables Have UDF (Attribute) Columns using the Oracle Data Dictionary

You can find additional tables by using the Oracle Data Dictionary module. This module displays other useful information about tables and fields as well.

1. **Open the Oracle Data Dictionary from the Admin menu.**
2. **Enter ATTRIBUTE1 in the Column Name field.**
3. **Select an Order By radio button.**

This selection determines how the returned will be sorted.

4. Select Search from the Actions list or press F8.

The system lists all of the tables that contain columns called Attribute1 (if Attribute1 is available in a table, then Attributes2 through 10 are also available). The list will include existing Custom views (beginning 'CV_') and interfaces ('SAIF_') in addition to tables ('SA_').

Once you have determined that a table contains Attribute columns, allowing you to place a User Defined Field on the associated window, you must insert a new record describing how the User Defined Field will look and function. This is done in the User Defined Fields (UDFs) module.

Workflow Groups Module

Using the WorkFlow Groups module you can build and maintain lists of users to simplify sending messages to groups of users within the system. Once a group is established it users can use it in a manner very similar to Distribution Lists in e-mail programs.

Fields

Group Owner

Only the Group Owner can use a given WorkFlow Group and the associated List of Values is limited to your username and Public.

User Name

The system automatically supplies your Username as the Group Owner. If you select this option, only you will be able to use the Group.

Public

If you select Public as the owner, any user that can sign onto the plant can use the list. No matter who the Group Owner is, the user must still establish the WorkFlow Group in their User Profile to access the list.

Group Name

The Group Name displays on the List of Values for the User field of the Message window, along with the first few words of the group description.

Description

The Description is for information purposes only, viewed only from within this module and on the User field of the Message window.

People in Group and People Not in Group

Taken together, these two columns include all the Users for the plant. Clicking the appropriate button between the columns moves names from one column to the other.

The Add Button

If you highlight a name in the People Not in Group column and click this button, the system moves the name to the People in Group column.

The Add All Button

If you click this button without highlighting a name the system moves all the remaining names from the People Not in Group column to the People in Group column. Note: When you use either of the All buttons the system automatically saves the changes for you and the Cancel button cannot be used to undo the change.

The Remove Button

If you highlight a name in the People in Group column, and click this button the system moves the name to the People Not in Group column.

The Remove All Button

If you click this button without highlighting a name the system moves all the remaining names from the People in Group column to the People Not in Group column. Note: When you use either of the All buttons the system automatically saves the changes for you and the Cancel button cannot be used to undo the change.

Copy Group

You can duplicate a group by selecting Copy Group from the Actions list.

Chapter 3

Resource Subsystem

Account Structure Module

The system displays and maintains account information as though the system had been designed with your specific account structure in mind.

Define your organization's account structure in the Account Structure module. Once you have defined the structure the system displays all Account Number fields using the defined structure. The system also uses the defined structure to support the Account Help window, which can be used to assist in finding a particular account by building it segment by segment.

Caution: After you have defined the Account Structure, careful consideration should be given before changing it because you also have to modify all associated data and any interfaces that use your Account Numbers.

Fields

Segment Name

The Segment Name indicates the label that the system will show on the Account record for that segment. The Account records can be found in the Account module in the Resource subsystem.

Length

The Length field indicates how many characters will be in the segment. This is the maximum number of characters, but if a user enters less than the maximum, the system still displays the positions for the other characters as blanks.

Use Code Table?

Checking this box will cause the associated code table (251-260) to be required by the person setting up the account. If the box is not checked, the LOV will still allow the user to select from the code table, but the use of the values in the LOV is not mandatory.

Required?

Placing a check in the Required check box indicates that the segment must be entered.

Delimiter Character and Position Indicator

You can use the Delimiter field to determine the character shown between segments of the account number. Placing a check in the check box indicates that the delimiter is to be shown whether or not the preceding segment contains a value. For example, with a three-segment account number using dashes as the delimiter characters, the system would show 1- -3 if there was no data in the second segment and both check boxes were checked. The system would show 1 -3 if there was no data in the second segment and only the second check box was checked.

The lines between the Required check boxes and the Delimiter Character field do not represent anything and should be ignored.

Code Tables

Code Table 251 to Code Table 260: ACCOUNT SEGMENT 1 to 10

Define values associated to each account segment defined in the Segment Name fields of the Account Structure module. For example, if Segment 1 is labeled Personal ID then the description for Code Table 251 would be "Personal ID" and the code list would show the Personal ID's that should show on the List of Values in the Account module. These IDs can then be used to create the accounts.

These are DBA type Code Tables, and great consideration should be taken before modifying them.

Accounting Periods Module

Fiscal or Accounting Periods are defined in the Administration subsystem. No gaps in date ranges are allowed in the input of Accounting Periods. Completion of the entries in the Accounting Periods module is mandatory for End of Period Processing to capture, roll up and reset period accounting information.

Business Rules

Account Period Override Rule

Type of Transaction	Acct Period	End Date
ADJUSTMENT		05/21/2004
INVOICE		05/21/2004
LABOR		05/21/2004
ODC		05/21/2004
SERVICE INVOICE		05/21/2004
STOCK		05/21/2004

Enter account periods that should be overridden during batch costing procedures.

Standard processing uses a transaction date to determine the correct accounting period. The accounting period that brackets the transaction date is used by default. This rule allows you to enter an accounting period to override the standard. If the costing procedures find an entry in this rule the accounting period related to the type of charge will override the standard processing. This is important at the end of accounting periods or accounting years so costs can be “back-dated” into the previous period.

To override the accounting period, enter a new account period year and month for each type of transaction. If no entry is made or if the period year and month are blank, then standard processing is used.

Pay Periods Module

Pay Periods are defined in the Administration subsystem. No gaps in date ranges are allowed in the input of Pay Periods. Completion of the entries in the Pay Periods module is mandatory for Pay Period Processing to capture, roll up, and validate timekeeping pay periods.

Business Rules

End of Period Processing Rule

The screenshot shows a configuration window titled "Business Rule END OF PERIOD PROCESSING". It includes fields for Rule ID, Description, and Comment. Below these is a table for "Process Date Rule" with columns for the rule name and the last run date. A description field at the bottom explains that the date is set by a database procedure.

Process Date Rule	Last Run
DATE_OF_LAST_MONTHLY_RUN	27-JAN-2004
DATE_OF_LAST_YEARLY_RUN	06-JAN-2004
OT AVERAGING BATCH WEEK START	
OT YEAR LAST PROCESSED	2003
OVERHEAD YEAR LAST PROCESSED	2004
OVERHEAD YEAR LAST RUN	31-DEC-2004
PERIOD_LAST_PROCESSED	200401
PYROLL_PERIOD_LAST_PROCESSED	200502
PYROLL_PERIOD_LAST_RUN	31-JAN-2005
PYROLL_YEAR_LAST_PROCESSED	2003
PYROLL_YEAR_LAST_RUN	
SICK_LEAVE_LAST_PROCESSED	

The End of Period Processing rule controls End of Month, End of Period, End of Payroll, End of Year Processing and Sick Leave Processing. This rule sets the system to review when batch processing was last done by period and by date.

It is recommended that the rule is run based on your set accounting periods. The job processes records for the period that is PRIOR to the current period, so we recommend midnight on the day following the last day of the accounting period. For example, if the period ends on July 15, set the job to run on July 16, 12:00am.

[Click here](#) for detailed processing steps.

Process Date Rule

DATE_OF_LAST_MONTHLY_RUN - the date End of Month Processing was last run. The SDBP_END_OF_PERIOD_PROCESSING batch process first reads the date of the last monthly run then writes a message to the Job Log record the value.

DATE_OF_LAST_YEARLY_RUN - the date End of Year Processing was last run. The date is set and maintained by the database procedure SDBP_END_OF_PERIOD_PROCESSING.

OT AVERAGING BATCH WEEK START - a system maintained field for the start date of the week used by the database procedure SDBP_AVERAGE_OVERTIME.

OVERHEAD YEAR LAST PROCESSED - The last year for which Overhead Regulatory Account cost allocation was done.

OVERHEAD YEAR LAST RUN - The date on which the last yearly Overhead Regulatory Account cost allocation was run.

PERIOD_LAST_PROCESSED - the period year and number End of Period Processing was last run. Periods are defined and maintained by you in the Accounting Periods module in the Administration subsystem.

PAYROLL_PERIOD_LAST_PROCESSED - the period year and number Payroll Period Processing was last run. Periods are defined and maintained by you in the Pay Periods module in the Administration subsystem.

PYROLL_PERIOD_LAST_RUN - the date Payroll Period Processing was last run. The date is also set and maintained by the database procedure SDBP_POST_TIMESHEET.

PYROLL_YEAR_LAST_PROCESSED - the year End of Year Payroll Period Processing was run. The year is set and maintained by the database procedure SDBP_CREATE_NEW_LEAVE_YEAR.

PYROLL_YEAR_LAST_RUN - the date End of Year Payroll Period Processing was run. The year is set and maintained by the database procedure SDBP_CREATE_NEW_LEAVE_YEAR.

SICK_LEAVE_LAST_PROCESSED - the date sick leave was last processed. This date is set and maintained by the database procedure SDBP_MONTHLY_SICK_LEAVE.

Last Run

Shows the date and time that the batch procedure was run last.

End of Period Processing Analysis

The following describes the End of Period processing steps.

1. Reads the **DATE_OF_LAST_MONTHLY_RUN** from the **END OF PERIOD PROCESSING** business rule.
2. Writes a message to the Job Log as "Value for **DATE_OF_LAST_MONTHLY_RUN** is: " followed by the value from the business rule.
3. Reads the **PERIOD_LAST_PROCESSED** from the **END OF PERIOD PROCESSING** business rule.
4. Writes a message to the Job Log as "Value for **PERIOD_LAST_PROCESSED** is: " followed by the value from the business rule.
5. Reads all records from **sa_accounting_periods** where the **period_year** | **period_month** is greater than the value found in **PERIOD_LAST_PROCESSED** (step 4). These records are returned ordered by **period_year** and **period_month**, so the next month to process will be at the top of the list.
6. Reads the data from the first record (specifically **end_date**) found in the list in step 5.
7. If the **end_date** is greater than the current date, then the process assumes the period is still current. The process stops and a message is written to the log, "Period is not ready to be processed."
8. The process check to see if the storeroom usage records have already been created for some reason. If storeroom usage records are found for the period being processed, the process stops and a message is written to the job log, "Period has already been run."

-
9. The next record in the list is read and the "period_year" for the two records is compared. If the years are different then the process sets a flag to note that year end processing should also be run. See step 12.
 10. Reads all records in the Storeroom table that have "month to date usage" quantities greater than 0. If then loops over each record processing steps 11 and 12.
 11. For the current Stock Item, the Month to Date Usage is set to 0, and the activity indicator is set to Y.
 12. A Storeroom Monthly Usage record is created that contains the Month to Date Usage value from the Storeroom record found in step 10.
 13. If the year end processing should be run, based on the information processed in step 9, then step 14 is performed.
 14. For all records in the storeroom, the Year to Date Usage is set to 0, and the activity indicator is set to Y.
 15. Updates the END OF PERIOD PROCESSING business rule, PERIOD_LAST_PROCESSED key, with the current period_year || period_month just processed.
 16. Updates the END OF PERIOD PROCESSING business rule, DATE_OF_LAST_MONTHLY_RUN key, with sysdate.
 17. If the year end process was run, the END OF PERIOD PROCESSING business rule, DATE_OF_LAST_YEARLY_RUN key, is updated with sysdate.
 18. The final message "Total Number of Records Processed: xxxx" is written to the job log.

Department Module

Fields

Department and Description

Department names are user defined. Use the description field to further explain the code.

Parent and Child Department Fields

These fields should be filled in if applicable. If you enter a Parent Department on a Department record, that Department will appear as a Child Department on the record for the Parent entered.

Charts

S_CHT126 - Departmental Costs Summary

A comparison of Budgeted costs to Actual costs for the current year and the previous year. The data can be filtered further by plant, department and area.

Copy Record

DEPT- COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Area Module

Fields

Department and Description

Enter the code for the Department that the Area is a division of. The system populates the description field from the Department module.

Area and Description

Create a unique Area code and enter a description of the designated Area.

Copy Record

AREA - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Account Module

Fields

Account Number

The system creates the Account Number after you enter values for each segment.

Department and Area Fields

Select the Department and Area that the asset relates to.

Reference ID Field

If your account structure does NOT require that employees charge time against the account when they enter their time, the Reference ID is optional. Reference ID allows you to associate the Account Number with a unique ID that you can use elsewhere in the system to retrieve the entire Account Number automatically. The Reference ID code must be unique to the account.

Typically, the system does not require a Reference ID number to enter an account number. However, in the Timekeeping module, the system requires a Reference ID when employees charge time against an account. Make sure that you configure Reference IDs for accounts that will be charged for labor.

Work Request Route Field

You can enter a default approver route in this field. If the DEFAULT APPROVER FROM ACCOUNT value in the Work Request Processing Business Rule is set to ON, the system will use the approval route entered in this field when a new Work Request is created and no approval route is entered. This saves anyone who is creating a Work request from having to know the appropriate title for the approval route. The approval route can always be overwritten on the Work Request if necessary.

The Work Request Route field is controlled by a List of Values that the system builds using the Approval Limits module of the Administration subsystem.

Budget Type Field

The Budget Type field indicates how Budget values will be calculated for this Account number. Select Annual to use costs incurred within the current calendar year to calculate the budget and committed costs for the account. Select Lifetime to use all costs every incurred against the account to calculate the budget and committed costs for the account.

Business Rules

Budget Checking Rule

The screenshot shows a configuration window titled "Business Rule BUDGET CHECKING". It includes fields for Rule ID (BUDGET CHECKING), Business (Business), Parameter, and Limit?. The Description field contains: "Use this rule to determine whether or not the system should check against budgets when processing cost related records. You can also determine whether budget checking will be based on Accounts, on". The Comment field contains: "The system checks any budget by taking the year-to-date sum of the budget and subtracting the existing commitments for the same time period for the same account or expense code to determine the budget". Below these is a table for "Budget Checking By" and "Option Status":

Budget Checking By	Option Status
ACCOUNT	OFF
EXPENSE CODE	OFF

The Description field at the bottom contains: "When the ACCOUNT rule key is set to ON and the EXPENSE CODE rule key is set to OFF the system verifies that approval of the record being processed will not cause the account(s)".

Use this rule to determine whether or not the system should check against budgets when processing cost related records. You can also determine whether budget checking will be based on Accounts, on Expense Codes, or on both.

The system checks any budget by taking the year-to-date sum of the budget and subtracting the existing commitments for the same time period for the same account or expense code to determine the budget balance. If the record being processed will cause the account or expense code to go over budget the system will proceed with the action indicated in the Budget Checking by Document business rule.

The Account/Expense Code combination can be represented in the following manner:

Budget Checking By Option Status

ACCOUNT - OFF

EXPENSE CODE - OFF

The system does not check budgets when processing cost related records.

ACCOUNT - ON

EXPENSE CODE - OFF

The system verifies that approval of the record being processed will not cause the account(s) indicated on the record to go over budget. With this setting, individual expense codes can go over budget, as long as they do not cause the overall account to go over budget (i.e., one expense code can "borrow" budget dollars from another expense code).

ACCOUNT - OFF

EXPENSE CODE - ON

The system verifies that approval of the record being processed will not cause the expense code (s) indicated on the record to go over budget. With this setting the overall account will not be allowed to go over budget because all of the expense codes that make up the account will be kept at or under budget.

ACCOUNT - ON

EXPENSE CODE - ON

The system checks both the overall budget amount for the account and the overall budget amount for the expense code to make sure that neither goes over budget. You might want to use this setting if you plan to allow budget overrides in normal processing so that if one expense code is allowed to go over budget and the approval of another expense code would cause the entire account to go over budget

(even if the expense code itself would remain under budget), the system would catch the budget overrun on the account.

Budget Checking by Document Rule

The screenshot shows a configuration window titled "Business Rule BUDGET CHECKING BY DOCUMENT". It includes fields for Rule ID, Desc, and Comment. Below these is a table with columns for Document, Action, and Alert User. The table lists document types such as BLANKET TO PO, CHANGE ORDER, CHECKOUT REQUEST, COST ADJUSTMENT, DIRECT CHARGES, PURCHASE ORDER, REQUISITION, and WORK ORDER, all with an Action of "IGNORE". The Alert User field is populated with "RAY" for most entries and "BRANWEN" for "COST ADJUSTMENT" and "FRED" for "DIRECT CHARGES". A Description field at the bottom contains the text "Controls Budget checking for Blanket top PO documents."

Document	Action	Alert User
BLANKET TO PO	IGNORE	RAY
CHANGE ORDER	IGNORE	RAY
CHECKOUT REQUEST	IGNORE	RAY
COST ADJUSTMENT	IGNORE	BRANWEN
DIRECT CHARGES	IGNORE	FRED
PURCHASE ORDER	IGNORE	RAY
REQUISITION	IGNORE	RAY
WORK ORDER	IGNORE	RAY

Use this rule to identify unique processing for the budget checks performed during approvals for certain documents. For each document, clients can establish whether the user will be warned that the budget will be exceeded, with the option to continue, or whether they will be stopped from approving the document if the budget will be exceeded or whether the system is to ignore giving the user budget information during approvals (still performs the budget check and alerts the appropriate users when exceeded). For each document, a user can be identified to receive an alert that a document has been approved or charges posted by batch that result in budget overruns.

Document

Indicates the type of document that will be checked for budget constraints.

Action

IGNORE - The system will not take any action if the budget amount will be exceeded when the record is approved.

STOP - The system will stop processing on the document indicated if the budget amount is exceeded.

WARN - The system will display a warning message to the approver if the budget amount will be exceeded when the record is approved.

Alert User

Enter the username of the person that should receive an alert when the document type indicated exceeds the budget. If you leave this field blank, the system will still display a warning message on the screen during processing of the record (if the Action field is set to WARN), but will not send a system alert to anyone.

You can enter additional users in the Notification view of the Accounts module.

Budget Checking Skip Accounts Rule

The screenshot shows the configuration window for the Business Rule BUDGET CHECKING SKIP ACCOUNTS. The window title is "Business Rule BUDGET CHECKING SKIP ACCOUNTS". The Rule ID is "BUDGET CHECKING SKIP ACCOUNTS". The Business is set to "Business". The List is set to "List". There is a checkbox for "Limit?". The Description is "This rule is used by the Budget Checking process. It contains the list of account codes, expense codes, or account code - expense code combinations that should be exempt from the budget checking process." The Comment is "Due to column size constraint please scroll to the right to enter Account and Expense data in KEY_VALUE4 and KEY_VALUES respectively." Below the comment is a table with three columns: Sequence No, Account No., and Expense Code. The table has three rows. Below the table is a Description field with the text "Inventory Expense".

Use this rule to list the account codes, expense codes, or account code - expense code combinations that should be exempt from the budget checking process. Placing an asterisk (*) in either the account code or expense code field in the Rule Keys section of the rule denotes a wild card. For example, if you enter account number 1234-5678 and expense code, all budget checking related to account numbers 1234-5678, regardless of the expense code on the transaction, will be skipped.

Expense Codes Rule

The screenshot shows the configuration window for the Business Rule EXPENSE CODES. The window title is "Business Rule EXPENSE CODES". The Rule ID is "EXPENSE CODES". The Business is set to "Business". The List is set to "List". There is a checkbox for "Limit?". The Description is "This rule lists expense codes and designated category." The Comment field is empty. Below the comment is a table with four columns: Expense Code, Category, Valid Capital, and Report Label. The table has five rows. Below the table is a Description field with the text "Inventory Expense".

Expense Code	Category	Valid Capital	Report Label
00001	Inventory Stock		INVENTORY
00002	Direct Stock		PURCHASE
00007	Leave Expense		MISCELLANEOUS
00010	Direct Charges Exper		
00013	Invoice with PO		

List expense codes and a category for each (such as regular labor, premium labor, stock purchases, direct purchases, etc.).

Expense Code and Category

Enter the valid code (used for accounting) in the EXPENSE CODE column. For each listed code, you can then enter the appropriate category into the CATEGORY column. These codes are used to summarize and categorize costs.

Note: Expense Codes are used with Account numbers to set up budgets for an entity.

CCB Expense

If your organization uses CCB Integration the CCB Expense column defines categories that are used to summarize costs when they are sent to Oracle Utilities Customer Care

and Billing from Oracle Utilities Work and Asset Management on the completion of a service request. these codes should correspond to a Characteristic Type in Oracle Utilities Customer Care and Billing. The list of values for this field is defined in code table 1195 - CCB Expense.

Valid Capital

The Valid Capital column is designated for a custom configuration and is not used.

Code Tables

Code Table 251 to Code Table 260: ACCOUNT SEGMENT 1 to 10

These code tables control the lists of values for the segments in the Account module.

Code Table 1195 - CCB Expense

If your organization uses CCB Integration, use this table to define codes to use with the Expense Codes business rule.

Code Table 1196 - CCB Install Remove Flag

If your organization uses CCB Integration, use this table to define flag codes.

Copy Record

ACCTDATA - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

View External Actual Costs

Allows users to view the External Actual Amount, Budget Balance and Actual Quantity columns on Period Costs and Cost Summary views. These columns contain data from your organization's external financial system.

Reports

S_RPT204 - Purchase Order Expensing Account Detail Report

Lists Purchase Orders by Expense Code.

Views

Period Costs

Enter budget amounts for each account according to period in the Period Costs view.

Account Distribution Module

Account Distribution Templates are used in the Requisition, Purchase Order, Blanket Contract, and Blanket Contract to Purchase Order modules.

Fields

Sequence No.: Account Distribution ID

The record number is comprised of a unique ID (Ex. "ACC0000013"). Account Distribution record numbers are typically set to be system generated.

TABLE NAME - SA_ACCOUNT_DISTRIBUTION - The table for which the sequence number is generated.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Batch Processes

ACCOUNT DISTRIBUTION TEMPLATE - sdpb_default_accounts_status

You are able to set future start dates in the Account Templates module. This process runs today's start dates and sets those records to active on that day.

Copy Record

ACCTTMPL - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Regulatory Account Module

Use the Regulatory Account module to define the FERC, PUC and FCC accounts required by your organization, and to associate these accounts with the appropriate account treatments and usage codes. As compatible units are planned against Work Order Task records, costs are applied to these accounts.

Fields

WIP Account

The list of values for this field is derived from other active Regulatory Account records that were created with Work In Progress designated in the Accounting Treatment field. Use these accounts to track costs for work while it is in progress.

Usage Code Field

If you try to select a Usage Code on a record and the list of values does not show any entries, there could be one of two reasons why there are no codes.

1. The Regulatory Account Usage Codes Business Rule must list at least one Usage Code associated to the Account Type selected.
2. There may already be another active Regulatory Account record set with the Account Type and Accounting Treatment combination selected on the current record. The system only allows ONE record with a particular Account Type/Accounting Treatment combination.

Overhead Class

List of values is controlled by the Regulatory Acct Overhead Class Business Rule. This field is only updatable when the account treatment is Overhead.

Business Rules

Regulatory Account Usage Codes

The screenshot shows a software window titled "Business Rule REGULATORY ACCOUNT USAGE CODES". It contains several fields and lists:

- Rule ID:** REGULATORY_ACCOUNT_USAGE_CODES
- Business:** Business
- List:** List
- Limit?:**
- Desc:** This rule is used to define the usage codes and associate them to a Regulatory Account Type. A Usage Code is entered on a Regulatory Account and supports the Compatible Units process.
- Comment:** Use the description field to enter a brief explanation of the Usage Code.
- Usage Code List:** A1, A2, HY, L1
- Account Type List:** FERC, FERC, FERC, FERC
- Description:** Usage Code - wooooohool

Define the usage codes used on Regulatory Account and Compatible Units records. Also associate these codes to a regulatory account type such as FERC, FCC, or PUC.

Usage Code and Account Type

Define codes appropriate to your business practices and associate them to an account type.

Regulatory Account Options

Business Rule REGULATORY ACCOUNT OPTIONS

Rule ID: REGULATORY_ACCOUNT_OPTIONS Business Parameter Limit?

Desc: This rule defines optional processing for Regulatory Accounts.

Comment: The Status column provides the ability to turn the associated Option on or off. The Account column defines the value to be used when the Option Status is ON.

Option	Status	Account	Frequency
FCC PRIOR YEAR REVERSAL ACCT	OFF		
FERC PRIOR YEAR REVERSAL ACCT	OFF		
INDIRECT OVERHEAD ALLOCATIONS	ON		MONTHLY
PRIOR YEAR REVERSAL EXPENSE	OFF		
PUC PRIOR YEAR REVERSAL ACCT	OFF		

Description: Used to define the frequency for Indirect Overhead Allocations. Enter "ON" in the status column to perform allocations and select "Monthly" or "Annually" in the Frequency column to define the frequency.

Determine how regulatory accounts are processed within the system.

FCC PRIOR YEAR REVERSAL ACCT - Used to define the regulatory account to be used for reversal of costs from prior years for FCC Account Types. Enter "ON" in the Status column to define a separate regulatory account for the reversal charges. Enter "OFF" to have the reversal charges applied to the same regulatory account as the original charges.

FERC PRIOR YEAR REVERSAL ACCT - Used to define the regulatory account to be used for reversal of costs from prior years for FERC Account Types. Enter "ON" in the Status column to define a separate regulatory account for the reversal charges. Enter "OFF" to have the reversal charges applied to the same regulatory account as the original charges.

INDIRECT OVERHEAD ALLOCATIONS - Used to define the frequency for Indirect Overhead Allocations. Enter "ON" in the status column to perform allocations and select "Monthly" or "Annually" in the Frequency column to define the frequency.

PRIOR YEAR REVERSAL EXPENSE - Used to define the expense code to be used for reversal of costs from prior years for all Account Types. Enter "ON" in the Status column to define a separate expense code for the reversal charges. Enter "OFF" to have the reversal charges applied to the same expense code as the original charges.

PUC PRIOR YEAR REVERSAL ACCT - Used to define the regulatory account to be used for reversal of costs from prior years for PUC Account Types. Enter "ON" in the Status column to define a separate regulatory account for the reversal charges. Enter "OFF" to have the reversal charges applied to the same Regulatory Account as the original charges.

Regulatory Account Overhead Class

Define overhead classes for estimating overhead allocation on Work Order Tasks.

Sequence Number

Use the Sequence number to specify the order in which the overhead class is distributed.

OH Class Type

Define the Overhead Class Type name in this free form field.

Estimated OH%

Use the Estimated OH% field to enter an estimate overhead percentage based on the Applied Type chosen.

Applied Type

Select a type from the list of values defined by the Expense Codes Business rule.

Description

Enter a brief description that will help users identify the overhead class they want to use. Along with the OH Class Type, the description displays on List of Values in the Regulatory Accounting module showing available Overhead Classes.

Batch Processes

Regulatory Account Cost - sdbp_regulatory_account_cost;

Posts costs associated to regulatory accounts.

Year End Overhead Distribution - sdbp_year_end_oh_cost_dist;

Allocates costs from the Overhead Regulatory Accounts to the related non-overhead accounts (Capital, Maintenance, Operations, Work In Progress) based on Overhead Class.

Process Fixed Assets - sdbp_work_order.fixed_asset;

Processes actual amounts and allocation amounts for a work order task and applies them to the Regulatory Accounts associated to the compatible units on the task. Also determines the value of fixed assets associated to the capital regulatory accounts on the work order tasks. This procedure also includes the package that creates change requests for the creation or retirement of group assets on a work order task.

Copy Record

REGACCT - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Storeroom Module

Business Rules

Available Quantity Calculation Rule

The screenshot shows a configuration window titled "Business Rule AVAILABLE QUANTITY CALCULATION". It includes fields for Rule ID, Business, List, and Limit. The description states: "This Business Rule defines the fields to be used in the equation to calculate available quantity in the storeroom." The comment field contains: "The equation will be: INVENTORY QUANTITY - (fields turned on)". A table lists quantity types and their status:

Quantity	Status
ALLOCATED	OFF
LOT HOLD	OFF
ON DEMAND	ON
ON HOLD	ON

The description field contains: "This Option is only for use with the Advanced Material Management option. Allocated Quantity in the Storeroom. This quantity will be used in the equation when this rule is ON".

Determine the quantities to use in the calculation of available inventory quantity for stock items.

Quantity and Status

Set the Status to ON or OFF to enable or disable the rule key.

ALLOCATED - This is an Advanced Material Management Option only. If this option is turned on, the allocated quantities will be subtracted from the inventory quantity to determine available quantity.

LOT HOLD - This is an Advanced Material Management Option only. If this option is turned on, the quantities on LOT HOLD will be subtracted from the inventory quantity to determine available quantity.

ON DEMAND - If this option is turned on, the quantities ON DEMAND will be subtracted from the inventory quantity to determine available quantity.

ON HOLD - If this option is turned on, the quantities ON HOLD will be subtracted from the inventory quantity to determine available quantity.

Invoice Setup Criteria Rule

Business Rule INVOICE SETUP CRITERIA

Rule ID: Business Parameter Limit?

Desc:

Comment:

Rule	Option
ALLOW ACCOUNT UPDATE	YES
ALLOW MISMATCHED INVOICING	YES
ALLOW NONTAX PRORATING	YES
DISPLAY ACCRUAL TAX TOTAL	YES
ERS NEXT APPROVER	RVMO01
INVOICE TOTAL COMPARE	NO
NEGATIVE DISCOUNT	NO
POST INVOICE	APPROVED
PRORATE	POSTED
SEND ALL BATCHES TO A/P	NO
SEND BATCH TO A/P	NO

Description:

Define how average unit price is calculated.

Rule and Option

ALLOW ACCOUNT UPDATE - If this rule key is set to YES users can override and change the Account for Inventory and Expense type stock codes on Invoice Line Items. User's responsibility profile must also contain the function, INVOICE ACCOUNT OVERRIDE.

ALLOW MISMATCHED INVOICING - If this option is set to YES it will allow an Invoice that does not match the Purchase Order to be recorded in the system. The system automatically puts such records into Pending Resolution status. After the mismatch has been resolved, batch processing changes the status to Approved.

ALLOW MULTIPLE POS - When this option is set to ON, you can record more than one purchase order per invoice. The system provides a Change PO button on the Matching to PO views and a Start Again option on the Quick Invoice Wizard where items from additional purchase order(s) can be recorded.

ALLOW NONTAX PRORATING - This option defines whether or not prorating to non-taxed line items is allowed or disallowed.

AVERAGE UNIT PRICE CALCULATION - Defines how the system calculates Average Unit Price (AUP) for a storeroom when the difference between the total amount of an invoiced item is greater than the total amount on the original purchase order item. If the rule is set to OFF, the entire difference is applied evenly among the Storeroom Item On Hand Quantity. If the rule is set to ON, the difference per item is applied.

For example: Assume a brand new storeroom item. PO Item ordered and received for 10 items at \$1 each. Stock Checkout of 8 items, thus On Hand Quantity is 2. Then invoiced at \$2 for all 10 items.

If the rule is set to OFF, the AUP will be \$6.00 (\$1 + Difference divided by On Hand

Quantity).

If the rule is set to ON, the AUP will be \$2.00. (\$1 + difference per item).

COPY PO ATTACHMENTS - When this option is set to YES, all existing attachments associated to the Purchase Order header are copied to the new Invoice record. Also any attachments associated to the Purchase Order line item are copied to the new invoice during the Matching to PO process. The default setting is NO.

DISPLAY ACCRUAL TAX TOTAL - Set this option to YES to display the accrued tax total on the invoice header.

ERS NEXT APPROVER - Identifies the next approver for Auto Invoices that have received more items than were ordered.

INVOICE TOTAL COMPARE - Set this option to 'YES' to display a warning when the manual invoice total field and the invoice total amount fields do not match. The warning message be displays when the user attempts to change status to Pending Approval.

NEGATIVE DISCOUNT - Set this option to YES to allow a negative number to be entered in the Discount Rate field on the invoice header. Do this if you want to markup (increase) the item total by the percentage entered.

OVERRIDE DISCOUNT AMOUNT - If this option is set to YES, the Invoice Discount Amount can be manually updated with a new value when the Invoice has an Item Total Amount. When the Invoice Discount Amount is manually updated the Invoice Discount Rate is recalculated appropriately. When the option is set to NO, the Invoice Discount Amount is calculated based on the Discount Rate and cannot be updated manually.

POST INVOICE - This option determines when invoices are posted throughout the system.

If Post Invoice is set to Approved (Default), the system posts invoices when invoices are in Approved status.

If Post Invoice is set to Sent to A/P, the system posts invoices when the invoice status is set to Approved and the Sent to A/P indicator is set to 'Y'.

If Post Issue is set to Paid, the system posts invoices when the invoice status is set to Approved and the Paid Indicator is set to 'Y'.

PRORATE - This option determines when the prorating procedure is executed.

If this option is set to APPROVED, the prorate procedure will be executed when the Invoice status is set to Approved. The user will not be allowed to set the status of the Invoice record from APPROVED back to CREATED.

If this option is set to POSTED, the prorate procedure will be called during batch processing when the Invoice is set to Posted. Status changes from APPROVED back to CREATED are allowed with this setting.

SEND ALL BATCHES TO A/P - Set this option to YES to display the Send All Batches to A/P action in the Invoice Batch module.

SEND BATCH TO A/P - Set this option to YES to display the Send Batch to A/P action in the Invoice Batch module.

Storeroom Demand Allocation Rule

Option	Status	Value
CHECKOUT REQUEST DEMAND	YES	
EXPIRATION OF REQUEST DEMAND	NO	14
INCLUDE RFQ	YES	
RESOLVE UNSUPPORTED ALLOCATION	NO	

Description
This will enable the demand quantity for checkout requests that are not already set from a work order. The requested quantities for OPEN requests will be included in the on demand quantity.

Set up processing for storeroom demand and allocation.

Option, Status and Value

CHECKOUT REQUEST DEMAND - (YES/NO) If this rule key is set to YES, checkout requests in ACTIVE status will be counted in the demand quantity shown in the Storeroom Pricing view of the Storeroom module, and will be factored in whenever Storeroom demand is calculated. If the rule key is set to NO checkout requests will not be included in any demand quantity calculations. If the rule key is changed from NO to YES the system does not recalculate existing quantities, but will begin to include ACTIVE checkout requests in calculations made after the change.

INCLUDE RFQ - This rule key determines whether the quantity on Request for Quotes line items in CREATED, APPROVED or ISSUED status which originated from an Approved Requisition are to be included in the Pending Order quantity field on the Storeroom Pricing screen.

EXPIRATION OF REQUEST DEMAND - (AMMO ONLY) - Not used.

RESOLVE UNSUPPORTED ALLOCATION - (Advanced Materials Management Option ONLY) - Not used.

Code Tables

Code Table 69: Reorder Reviewer Code

Reviewer Code - Define codes to assign reviewers for specific stock items. This field is searchable on the Storeroom Search Options screen enabling you to categorize Reorder Review items by reviewer.

DBA Code

Code Table 187: Inventory Adjustment Reason Codes (Inventory Quantity Adjustments Action)

Adjustment Reason field - Define reasons for adjusting inventory quantities. Typical values may be Bad Inventory Count, Error Correction, Shrinkage, etc.

Copy Record

STORERM -COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Reorder Wizard

Grants the ability to create and approve reorder records.

Storeroom ABC

Grants access to the ABC Processing Options view in the Storeroom module.

Storeroom Adjustment

Grants access to the Adjust Inventory Quantity action in the Storeroom module.

Storeroom Reorder

Grants the ability to modify the Stores Reorder fields on the Storeroom Pricing view of the Storeroom module.

Batch Processes

Cost Invoice - sdbp_cost_invoice.cost_invoice;

Processes costs for purchase Invoices, selecting approved Invoices and posting costs throughout the system as required. Once an Invoice is successfully processed, it is marked as posted.

Cost Stock - sdbp_cost_stock.cost_stock;

Processes costs for stock transactions that have not yet been posted. Information is selected from the table SA_INVENTORY_LOG and posted throughout the system as required. Once a stock cost transaction is successfully processed, it is marked as posted.

End of Period Processing - sdbp_end_of_period_processing;

Processes storeroom data at the end of each accounting period, populating the Storeroom Usage table and resetting the Storeroom Month-to-Date (MTD) Usage quantity to zero.

Reset Demand Quantity - sdbp_storeroom_demand;

Recalculates the On-Demand Quantity for parts within the storeroom. This procedure reviews all active work order tasks, summing the quantities required across tasks for stock items. Once recalculated, the On-Demand Quantity for each storeroom item is updated accordingly. Note that this batch procedure is not a required procedure since standard processing maintains the storeroom On-Demand Quantity. This serves as an extra level of assurance that the On-Demand Quantities are correct as of each nightly batch run. Note that running this process could potentially be time consuming if there is a large amount of data for the system to process.

RESET ON ORDER QUANTITY - sdbp_storeroom_on_order;

Resets the quantity for storeroom parts that are on order. This procedure is triggered when a PO is canceled.

Stock Reorder - sdbp_stock_reorder.stock_reorder;

Reviews all storeroom items, selecting those that are set up for automatic reorder and processes those items that have reached their reorder point. This process uses settings in the Batch Stock Reorder Business Rule to calculate the quantity to reorder. The basic calculation is:

"Quantity to order" = Reorder quantity + (reorder quantity * greatest((Max quantity - inventory quantity - on order - in receipt - transfer q - reorder quantity + on demand - repair quantity) / reorder quantity, 0))

You can set a custom batch process to run SDBP_STOCK_REORDER on a specific storeroom by entering that storeroom in the job parameters.”

Storeroom Demand - sdbp_storeroom_demand;

Recalculates the On-Demand Quantity for parts within the Storeroom. This procedure reviews all active Work Order Tasks, summing the quantities required across Tasks for stock items. Once recalculated, the On-Demand Quantity for each Storeroom item is updated accordingly. Note that this batch procedure is not a required procedure since standard processing maintains the Storeroom On-Demand Quantity. This serves as an extra level of assurance that the On-Demand Quantities are correct as of each nightly batch run. Note that running this process could potentially be time consuming if there is a large amount of data for the system to process.

Storeroom Repair Costs - sdbp_storeroom_repair_costs;

Sums costs based on the material and account log for material that has been dispositioned from closed work orders.

Charts

S_CHT127 - Inventory Turns

The number of turns per inventory item. The number of turns per inventory is calculated as follows: Usage Quantity / (Maximum Quantity - Reorder Point). The data can be filtered further by Plant, Stock Type and by time period. Other filtering options, including Storeroom and Stock Code, are available in the Chart Field List.

S_CHT128 - Inventory Valuation

The Total Value of each inventory item. The data can be filtered further by Plant, Storeroom, Stock Type and Stock Class.

Reports

S_RPT050 - Catalog Non-Usage Report

Lists Stock items (and the last 10 transactions) that have not been used for selected period of time.

S_RPT016 - Catalog (without Quantities) Report

Shows an inventory of Stock items by storeroom without displaying Item quantities.

S_RPT026 - Inventory Picklist Report

Lists Stock items to be issued from the storeroom and can be used to provide storeroom personnel a means to prepare Stock for pickup or delivery.

This list can be built by either planning Stock items on a work order before the work order is activated or by creating a checkout request.

Note: S_RPT026B is the bar code font version of this report.

S_RPT034 - New Stock Items Report

Lists Stock items that are new to the catalog.

S_RPT032 - New Storeroom Items Report

This report is a listing of Stock items new to storerooms.

S_RPT035 - Overstock Report

Lists Stock items where the quantity on-hand is greater than the maximum quantity. This information is retrieved from the Storeroom module of the Resource subsystem.

S_RPT202 - Purchase Order Inventory Item Cost Report

Displays Cost Summaries of all Purchase Orders made for "stocked" items to compare current purchase price with average unit price and calculate the price variance.

S_RPT115 - Stock Transfer Report

Lists Stock items to be issued from one storeroom and received in another.

Note: S_RPT115B is the bar code font version of this report.

S_RPT033 - Storeroom Activity Report

Lists storeroom transaction information over a selected period of time.

S_RPT017 - Storeroom Report with Quantities

Lists stock codes from the Storeroom module of the Resource subsystem. Quantity and price information is included.

S_RPT019 - Storeroom Value by Class

Lists total storeroom values by Class from the Storeroom module of the Resource subsystem.

S_RPT106 - Storeroom Value By Stock Code

Displays average values for storeroom items along with related information.

S_RPT083 - Tax Report for Inventoried Stocked Items

Provides a summary of taxable inventoried Stock items that have been used to maintain assets. These transactions represent an overpayment / underpayment of taxes.

S_RPT082 - Tax Report for Non-Stocked Items

Provides a summary of taxable non-stock items that have been used to maintain assets. These transactions represent an overpayment / underpayment of taxes.

S_RPT036 - Understock Report

Lists Stock items where the quantity on-hand is less than the maximum quantity. This information is retrieved from the Storeroom module of the Resource subsystem.

Storeroom Setup Module

Business Rules

ABC Inventory Rule

ABC Class	% of Items	% Over Safe	# of Months
A	10	30	2
B	20	20	4
C	70	10	12

Establish the parameters used to classify individual stock items in each storeroom as “A”, “B” or “C” class stock. These stock classes are based on the relative value of the prior twelve month's usage and item value and can be used to recalculate reorder parameters. Typically, A class items should be reordered more frequently than B or C class items.

Users working with ABC Inventory need to have the Storeroom ABC function in their responsibilities.

ABC Class

A class stock makes up the top value usage over the past 12 months. Items with this type class have a high dollar usage value.

B class stock makes up the next value usage over the last 12 months. Items with this type class have a dollar usage value in the middle; it is neither high nor low.

C class stock makes up the remaining value usage over the last 12 months. Items with this type class have a low dollar usage value.

% of Items

Indicates the percentage breaking point for the stock class listed in the “ABC Class” column (e.g. A class is 20%, B class is 30% and C class is the remaining 50%).

% Over Safe

Dictates the percentage over the safety level (minimum quantity) used to set the reorder point quantity.

of Months

The desired reorder frequency (in number of months) used to determine the maximum quantity.

Code Tables

Code Table 4: Storeroom Types (Length = 10)

Type field - Categorize the type of Storeroom record at a high level. Typical Storeroom Types can include QC (Quality Control), RECEIVING (Receiving Warehouse), REGULAR (Regular Storeroom), VIRTUAL (Virtual Storeroom), etc. Users can populate Code Table 4 with a logical grouping of storerooms that they have created to categorize storerooms.

Copy Record

STORESET - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Master Catalog Module

Fields

Sequence No.: Stock Code

The record number is comprised of a unique ID (Ex. "AUT_ALTDATE_001"). Stock Code record numbers are typically set to be created manually.

TABLE NAME - SA_CATALOG - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Business Rules

Procurement Level Rule (Associated Stock Codes View)

The screenshot shows a configuration window titled "Business Rule PROCUREMENT LEVEL". It contains the following fields and controls:

- Rule ID:** PROCUREMENT LEVEL
- Business:** Business
- List:** List
- Limit?:**
- Desc:** This Business Rule is used to define the list of valid Procurement Levels.
- Comment:** Valid Quality indicators are: QUALITY, NON-QUALITY and NOT USED
- Procurement Level:** A list with items A, B, and C.
- Quality Ind:** A table with rows for NON-QUALITY, QUALITY, and QUALITY.
- Apprd Vendor:** A table with rows for NO, YES, and NO.
- Description:** Procurement Level A (NON-QUALITY)

Procurement Level	Quality Ind	Apprd Vendor
A	NON-QUALITY	NO
B	QUALITY	YES
C	QUALITY	NO

Define a list of valid Procurement Levels.

Procurement Level

List the user determined procurement levels.

Quality Indicator

For each Procurement Level code, assign a Quality Indicator. The valid values are QUALITY, NON-QUALITY and NOT USED.

Approved Vendor

For each Procurement Level code, indicate whether or not an approved vendor must be used when purchasing items of this Procurement Level. Valid selections are Yes or No.

Shelf Life Rule (Associated Stock Codes View)

The screenshot shows the 'Business Rule SHELF LIFE' configuration window. It includes fields for Rule ID (SHELF LIFE), Business, List, and Limit?. The description states: 'This rule describes the parameters and values related to the shelf life of a stock item.' The comment reads: 'The value will be used in the calculation of expiration date. Delivery date + ('Value' * Shelf Life)'. Below this is a table for Shelf Life Type and Values:

Shelf Life Type	Values
INTERNAL	50
NONE	
VENDOR	

The description field contains: 'Used during receiving to calculate expiration date. Delivery date + "value" x shelf life.'

Determine the types of calculations that can be utilized to determine the expiration of Stock Item Lots.

Shelf Life Types

INTERNAL - The value will be used in the calculation of the expiration date. Delivery date + ('Value' * Shelf Life).

NONE - The value will be used in the calculation of the expiration date. Delivery date + Shelf Life.

VENDOR - The vendor supplies the expiration date.

Values

The value represents a percentage adjustment to be applied in the calculation of the expiration date.

Update Primary Vendor Rule (Associated Stock Codes View)

The screenshot shows the 'Business Rule UPDATE PRIMARY VENDOR' configuration window. It includes fields for Rule ID (UPDATE PRIMARY VENDOR), Business, Parameter, and Limit?. The description states: 'This rule dictates whether or not the Prime Vendor on the catalog is updated when a Purchase Order or the item is issued.' The comment field is empty. Below this is a table for Prime Vendor Rule and Option Status:

Prime Vendor Rule	Option Status
UPDATE_PRIME_VENDOR	YES

The description field contains: 'Should the system update Prime Vendor on the Catalog header when a Purchase Order for the item is issued?'

Set the system to update or not update the Prime Vendor on Catalog Stock Item records each time a Purchase Order that references the Stock Item is Approved.

Prime Vendor Rule and Option Status

UPDATE_PRIME_VENDOR - Options are YES or NO. If this rule key is set to YES, the Prime Vendor on Stock Item records is updated to the Vendor listed on each new approved Purchase Order. If the rule key is set to NO then the Prime Vendor on the Catalog record remains the same regardless of what is listed on Purchase Orders.

Code Tables

Code Table 212: Item Class Codes (Length = 10)

Class field - Classify Stock Items into groups. Typically, Class Codes are set up for high turnover items (to help in generating Physical Inventory lists). Classifying the Stock Items in this manner facilitates searches by allowing queries to be conducted at a high level.

Code Table 23: Unit of Measure (Length = 4)

Unit of Purchase (UOP) and Unit of Issue (UOI) fields - Define units codes. These fields are used by the system to maintain quantities as parts are issued and new parts are received. You may, for instance, issue in units of each ('EA') but order in units of boxes ('BOX') where one box would contain 10 individual items. Code Table 23 enables you to define the different Units of Purchase and Units of Issue.

Code Table 18: Purchasing Commodity Codes (Length = 20)

Commodity Code fields - Classify stock items by purchasing group. For example, a purchasing group might be in charge for ordering Lumber, Chemicals, Vehicles, etc. Classifying the Stock Items in this manner facilitates searches by allowing queries to be conducted at a high level.

Code Table 159: Federal Tax Codes (Length = 1)

Federal field - The code can only be one character long and the Description should contain the percentage rate in the first six characters of the field.

Code Table 160: State Tax Codes (Length = 1)

State field - The code can only be one character and the Description should contain the percentage rate in the first six characters of the field.

Code Table 161: Duty Codes (Length = 1)

Duty field - The code can only be one character long and the Description should contain the percentage rate in the first six characters of the field.

Code Table 122: Commodity Category Codes (Length = 5)

Category field - Commodity information can be especially helpful when trying to locate a specific stock code. Commodity Codes categorize and sub-categorize stock items, allowing you to create and maintain a descriptive structure used to quickly identify the type of part you are looking for, and from a much shorter list of stock items, locate the right one.

A sample Category Code might be Electrical or Instrumentation.

Link

Each Category Code points to its own Commodity Name Code Table. This Link field is where the Commodity Name Code Table number would be inserted. For example, if 'M' (for Mechanical) is chosen as the Commodity Code, the 'linked' table for Commodity Names would only contain values that pertain to the 'M' category.

Code Tables 122, 123, 124, 125, 128, and 129 work together to define one Commodity Code.

Code Table 123: Commodity Composition (Length = 10)

Composition field - Physical matter types are populated in this code table. Some examples might be Aluminum, Iron, Rubber, etc.

Code Table 6: Hazardous Types (Length = 10)

Hazardous field (unlabeled field under the Hazardous check box) - Define types of hazards. Some examples might be Flammable, Toxic, Poisonous, etc.

Code Table 360: Quality Classes

Quality Class provides another way to classify Catalog items in respect to Material

Control. The Quality Class will display on purchasing, receiving and inventory-related records. Some examples might be (High, Low, Medium)

Code Table 202: Storage Code (Length = 5)

Storage Code field - Classify catalog items by how they should be stored. Some examples might be (Temp controlled under 40 degrees, clean room storage, dry storage, etc.)

Code Table 203: Special Requirements (Length = 5)

Special Requirement field - Define catch-all codes to include any other miscellaneous special issues related to the catalog item. Some examples might be (Handle with Care/Fragile, Ship by Ground Transportation Only).

Code Table 209: Relationship Types (Associated Stock Codes View) (Length = 20)

Relationship Type column - Define how similar stock codes relate to one another. Some examples of data for this code table are: Complement, Other relationship type, or Substitute.

Copy Record

CATALOG - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Batch Processes

Create BOM Details - sdbp_create_bom_details.create_bom_details;

Provides an automated means of updating existing bill of materials with new stock codes based on other operations occurring in the system. Stock Code is added to the BOM ID related to Asset ID/Component ID information selected from SA_INVENTORY_LOG and SA_RECEIVING_LOG tables. Once a log record is successfully processed, it is marked as complete.

Charts

S_CHT127 - Inventory Turns

The number of turns per inventory item. The number of turns per inventory is calculated as follows: Usage Quantity / (Maximum Quantity - Reorder Point). The data can be filtered further by Plant, Stock Type and by time period. Other filtering options, including Storeroom and Stock Code, are available in the Chart Field List.

S_CHT128 - Inventory Valuation

The Total Value of each inventory item. The data can be filtered further by Plant, Storeroom, Stock Type and Stock Class.

Views

Crafts

Craft	Description
CARP	Carpenter
MECH	Mechanic
ELEC	Electrician

Associated crafts are for informational purposes only and are not used elsewhere in the system.

For each item in your catalog, you can create a list of crafts that typically use or are responsible for installation and maintenance of the item. You can only list a craft once per item.

Asset Module

Fields

Sequence No.: Asset ID

The record number is comprised of a unique ID (Ex. "ILB ASSET 1") and Asset Record Type (Ex. "E"). The system uses the combination of the Asset record type, and the Asset ID. Many clients use system generated sequence numbers for the Asset ID to ease the burden of creating, documenting, and maintaining a "smart" numbering system. However, some clients do choose to allow users to create this number manually. The number must be unique in either case.

TABLE NAME - ASSET - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Asset Class

Assign an asset class to the asset based on the classes defined in the Asset Class module.

Approval Route Field (Permit Template Requirements View)

Designate the Approval Route needed to verify the Permit Template assigned to the Asset. Approval Routes are created in the Routing List module under Approvals and Routes in the Administration subsystem.

Maintenance Manager

The value entered in the Maintenance Manager field on the Asset header determines which Maintenance Manager will bear the costs associated with the asset when work is done. The field is controlled by a list of values the system builds using the Maintenance Manager module in the Resource subsystem.

Business Rules

Asset Runtime Rule

The screenshot shows the configuration window for the 'Business Rule ASSET RUNTIME'. It includes fields for Rule ID (ASSET_RUNTIME), Business, Parameter, and Limit?. The description states: 'This rule defines how the Asset Runtime per month or per period will be calculated. The rule is used in conjunction with the stored database procedure SDBP_RUNTIME.' Below this is a table for 'Period/Month' and 'Status'. The first row is 'END OF MONTH' with 'ON' status. A description at the bottom explains: 'Enter OFF in the "STATUS" column to have SDBP_RUNTIME calculate the Asset Runtime from the beginning of one month/period to the beginning of the next month/period. Enter ON in the "STATUS" column to have SDBP_RUNTIME calculate the Asset Runtime from the end of one month/period to the end of the next month/period.'

Period/Month	Status
▲ END OF MONTH	ON

Define how the Asset Runtime per month or per period will be calculated. The rule is used in conjunction with the stored database procedure SDBP_RUNTIME.

Period/Month and Status

ALLOW LOWER RUNTIME - This key only affects assets with depreciation method of Units of Production. A Status of YES allows entry of a reading lower than or equal to the last reading. A Status of NO only allows entry of a reading higher than the last reading.

END OF MONTH - Entering ON or OFF in the status determines the period of time the SDBP_RUNTIME calculates the Asset Runtime from. ON calculates from the end of one month or period to the end of the next month or period. OFF calculates from the beginning of one month or period to the beginning of the next month or period.

Criticality Override Rule

The screenshot shows the configuration window for the 'Business Rule CRITICALITY OVERRIDE'. It includes fields for Rule ID (CRITICALITY_OVERRIDE), Business, Parameter, and Limit?. The description states: 'This rule allows the criticality field (selected from the Asset module) to be modified when copied to a Work Order or a Work Request. Such processing is appropriate when Asset records do not have the correct criticality assigned to them.' Below this is a table for 'Module' and 'Option Status'. The first two rows are 'WORK ORDER' and 'WORK REQUEST', both with 'ALLOW' status. A description at the bottom explains: 'The criticality field is not available for update in the Work Order and Work Order Task modules.'

Module	Option Status
▲ WORK ORDER	ALLOW
WORK REQUEST	ALLOW

Control modification of the Criticality field on Work Orders and Work Request records. The Criticality field is copied onto work records when an asset is referenced. Set the option status to Allow or Disallow to control whether or not the field can be modified. Allowing modification is appropriate if your Asset records generally have no criticality or an incorrect criticality assigned to them.

Default processing is DISALLOW. The Criticality field is the first Priority field on work

records.

Planner Rule

Code	Full Name	Username
123456	Max Length	BYB_USER_1
BYB1	Branwen Y. Burgess	BRANWEN
RLW	Ray Winther	RAY
RVM	Raya Veksler	RVEKSLER
SRP	sudha's	SREDDY
WWW	Nolan and Lauren's D	WILLY

Define planner codes, and identify the full names and usernames associated to each code. These codes are used when identifying a planner on work records.

The user associated with the code receives an alert when an event occurs where an alert would be sent to the planner. For example, when a planner plans parts against a work order and needs to be notified when the parts have arrived. This does not mean that the system is configured to send alerts regarding any record where a planner is indicated.

Code

Enter the codes for planners in the Code column. Each code must be unique.

Full Name

Enter the full name of the person associated with the code. A person can be listed on more than one code.

Username

Enter the username of the person associated with the code. Since a person can be listed on more than one code, the username can be listed more than once as well.

Asset Depreciation Rule (Depreciation View)

Depreciation Rule	Value
CONVENTION	FULL-MONTH
FREQUENCY	ANNUALLY
LAST PERIOD PROCESSED	200412
LAST RUN DATE	09-FEB-05

This rule determines how the system will process asset depreciation costs and post them to the account log.

Once the values for the Convention and Frequency rule keys are set and the depreciation batch job has run, the settings should not be changed. Any modification will result in irreversible errors in your depreciation calculations.

CONVENTION - Select Full-Month to indicate the amount of depreciation that can be claimed in the year the asset is placed in service. Full-Month is the only option.

FREQUENCY - The value entered here determines how often all asset's depreciation will be written to the account log. For example, if the Last Processed Date is '200301' and the frequency is monthly, the account log will have entries of '01 2003' and in the future, the following months (i.e. 02 2003, 03 2003). Valid frequencies are Monthly, Quarterly or Annually.

LAST PERIOD PROCESSED - The Administrator should enter an initial date in this field when the rule is configured. Once the date is set the system updates the date when the account depreciation batch process runs. Do not modify this rule key after initial configuration.

The proper date format is YYYYMM.

LAST RUNTIME DATE - Last Run Date will be updated by the system whenever the batch procedure runs.

Asset Key Segments Rule (Key Segments View)

Segment	Label	Length	Option
SEGMENT1	General	4	Y-
SEGMENT2	Street Number	4	Y-
SEGMENT3	Node Number	5	Y-
SEGMENT4	Lateral Number	3	Y-
SEGMENT5	Sequential Number	6	Y-

The Asset Key Segments business rule defines the Asset Key Flex Segments to customize Asset IDs. Each segment contains a label, length and options.

For more information regarding this feature, please refer to the Asset section of the Resource User Guide.

This functionality allows users to group Asset IDs to make it easier to locate the required asset. Since the system allows an infinite number of Asset IDs to be defined, Asset Key Segments can significantly aid in searching through very large databases.

To disable this Rule, the label field for SEGMENT1 must be null. If the rule is disabled, the Segments view does not appear in the Asset or Fleet Asset module, and the associated functionality is turned off.

Segment

The “SEGMENT” column determines which segment, or “piece”, of the Asset ID is being defined.

Label

The “LABEL” column describes the SEGMENT. It is the label displayed within the Asset module windows.

Length

The “LENGTH” column defines the maximum number of characters for the SEGMENT.

Option

The first character in the “OPTION” column indicates whether a code table is to be used: “Y” for YES, “N” for NO. The second character in the “OPTION” column is the delimiter for the SEGMENT.

To make any one SEGMENT a required field, use the Modules Administration - Forms module. You can also configure Special LOVs for these fields.

Code Tables

Code Table 25: Building Codes

Building field - Define codes for asset locations specific to the client organization. The

Building field is searchable from the Search Options screen, and can be useful in finding assets when only the building location is known.

Code Table 29: Asset Types

Asset Type field - Classify assets into defined groups. Classifying assets in this manner facilitates searches by allowing queries to be conducted at a high level. The Results of Search completed at the Asset Type level will contain valuable information that can be used to further narrow down user searches until the required Asset record is located. This code table is configured under the following modules: Procedure, Asset, BOM.

Code Table 40: Criticality Codes

Criticality field - The criticality number represents the relative work or safety impact of the asset. This number is later used by the system to calculate the overall priority of work orders.

The system contains default entries for Code Table 40, however, you can alter the data. We recommend that only the Description field be altered if necessary since the numeric values (1-9) are used in the calculation of priority on work orders and work requests.

Code Table 61: Sources Type for Isolation (Sources to Isolate View)

Type column - Types define the type of equipment which needs to be adjusted prior to working on a designated area. Examples of data are: Upstream Breaker, Downstream Breaker, Upstream Valve, Downstream Valve.

Code Table 62: Required Position for Isolation (Sources to Isolate View)

Lockout Position and Release Position columns - Define isolation positions to indicate the state that equipment which needs to be isolated should be in for safe working conditions. Some examples of data are: On, Off, Open, Closed.

Code Table 75 - 77: Asset Mobile fields 1-3

Asset Mobile fields - Define codes to use to filter assets when they are downloaded on a PDA.

Code Table 105: Specification Categories for Assets

Useful Life Units field - Define valid names for the types of measurement units that can be metered and tracked to determine asset operation.

Code Table 107: Units (Depreciation View)

Useful Life Units field - Define valid names for the types of measurement units that can be metered and tracked to determine asset operation.

Code Table 110: Backlog Group

Backlog Group field - Define backlog groups to group crews or to find and categorize work orders at a high level. This code table is used in the Process, Asset, Function, Work Request, Work Order, and Crew Activity Log module.

Code Table 130: Asset Interface Types - For Input / Output (Asset Interfaces View)

Interface Type field - Define codes to categorize interfaces between assets. These associations can enhance searching and grouping of asset relationships. Typical asset interface types may be Hydraulic, Electrical, Mechanical, etc.

Code Table 230: Asset Record Types

The first Asset ID field - Asset Record Type categorizes the type of Asset record at a high level. Typical Asset Record Types include "E" (equipment), "I" (instrumentation), "B" (building), and "R" (room). Users can populate Code Table 230 in accordance with the logical grouping of assets that they have created in their Asset Hierarchy. This grouping serves as a method of categorizing assets and a means searching for assets.

Note: When populating code table 230, fleet assets are "V" type. This value is hard coded

and therefore does not need to be entered.

If your organization uses a Lockout/Tagout system with the Asset and Permits modules, you may also want to create “T” type assets for Tag Points and select these as the Tag Point Asset IDs when setting up the Sources to Isolate record. This will enable you to reference an asset as both a tag point and as the primary asset on one record. If the asset is not configured in this way, the system will not allow you to reference the same asset twice on one Sources to Isolate record.

Code Table 231: Location

Location field - Define codes for asset locations specific to the client organization. The Location field is searchable from the Search Options screen.

Code Table 344: FMEA System Code

FMEA System field - Define codes for FMEA systems that assets belong to.

Code Table 1192: Riva Asset Type

RIVA field - Define codes for RIVA Asset types.

Copy Record

ASSET

Add this to users’ responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Create Activity Log From Asset

Grants the ability to create an asset activity log entry using the action on the Asset record.

Create Emergency Work Order Asset

Grants the ability to create an Emergency Work Order record using the action on the Asset record.

Create Work Order Asset

Grants the ability to create a Work Order record by selecting the action on an Asset record.

Create Work Request Asset

Grants the ability to create a Work Request record by selecting the action on an Asset record.

Create Specification

Grants access to the action that creates a specification attachment to the current Asset record.

View GIS

This enables the View GIS and Print GIS actions in modules that reference assets.

Reports

S_RPT089 - Asset Listing By Type and Class Report

Lists assets in the system.

S_RPT091 - Historic Cost Performance by Asset Report

Lists assets and work orders and their associated Labor and Material costs.

S_RPT090 - PM By Asset Report

Lists the PM Masters and subordinate PM Masters by asset.

S_RPT007 - Process Report with Asset Detail

Lists the processes created in the Process module of the Resource subsystem along with a breakdown of the assets attached.

Batch Processes

Cost Asset - sdbp_cost_asset;

Allocates costs to assets indicated on the Asset list in the Work Order Task module by creating cost adjustment records and posting accordingly. This functionality is only applicable when the Allocate Costs to Asset option in the Work Order Processing business rule is set to ON. You must either set the job run option to YES in the Batch Job Control business rule or set up an individual batch schedule for it to run automatically. The cost adjustment is not created until the work order is in closed status, so this should run after the close work order process. Please refer to the instructions under the Job Manager module for more information.

Create BOM Details - sdbp_create_bom_details.create_bom_details;

Provides an automated means of updating existing bill of materials with new stock codes based on other operations occurring in the system. Stock Code is added to the BOM ID related to Asset ID/Component ID information selected from SA_INVENTORY_LOG and SA_RECEIVING_LOG tables. Once a log record is successfully processed, it is marked as complete.

Depreciate Assets - sdbp_end_period_depreciation;

Depreciation costs are posted by batch according to settings in the Asset Depreciation business rule.

Charts

S_CHT148 - Planned Vs. Unplanned Downtime

A comparison of Planned Downtime to Unplanned Downtime for the current and the previous years. Downtime is considered to be “Planned” if the Downtime Scheduled indicator on the Asset Downtime record equals 'Y'. The data can be filtered by Plant. Other filtering options, including Department, Area and Asset, are available in the Chart Field list.

Metrics

S_MTRC6 - Percent of Planned Downtime - sdbp_metric_pct_plan_outage

This metric is to describe the relationship between Planned Outage time and the total outage time as a percentage. Planned Outage time is considered an occurrence of downtime for a given Asset if the downtime was scheduled. It provides a means to monitor and improve the ratio of planned Outage time versus total Outage time.

Views

Associated Permit Requirements

Asset ID	Description	Permit Template ID	Permit Type
ILB ASSET3	ILB Asset	ILBPT2	SAFE
ILBASST5	Asset 5	ILBPT1	SAFE
ILBAST4	Asset 4	ILB006	SAFETY
ILBAST200	2nd Level pumps for the ILB facility.		

List the assets that are associated with the primary asset.

For example, if a permit is to open and inspect a complex of high pressure steam pipes, the steam may need to be diverted through a different set of pipes, or the boiler may need to be shut down. In this case both the second set of pipes and the boiler might be listed as associated assets with their own permit requirements.

Asset Depreciation Accounts

	Accounts	Expense Codes
Asset Cost	RJB1-Y-ASSET P-ASSETC-WORK ORDER-004	00001
Depreciation Expense	RJB1-Y-ASSET P-ASSETC-WORK ORDER-004	00001
Accum Depreciation	RJB1-Y-ASSET P-ASSETC-WORK ORDER-004	00001
Disposal Gain/Loss	RJB1-Y-ASSET P-ASSETC-WORK ORDER-004	00001

Interfaces
Fixed Asset

If a depreciation method is selected for the asset, you must specify accounts and expense codes to use when calculating depreciation on the Depreciation Accounts view. The system supplies the depreciation account and expense code information for the property unit defined in the Asset Class module, but different codes can be specified for this asset if necessary.

Asset Interfaces

In/Out	Interface Type	Interface Asset	Interface Asset Description
IN	POWER	ILBASST5	Asset 5
IN	POWER	GBP_ASSET001	Quven's Asset - IC
OUT	POWER	ILBAST4	Asset 4

This view allows users to define how the displayed asset is physically related with other assets. This is achieved by identifying which assets feed into the listed asset, and which assets are fed by the listed asset. For example, a pump failure may affect hydraulic power to down-line assets, but not affect the electrical power. In this case, searching for interfaces with other assets of type 'Hydraulic' will produce a list of affected assets. Similarly, searching for interface types of 'Electrical' will produce a list of unaffected

assets.

Permit Template Requirements

The screenshot shows a web-based form titled "Asset E ILB ASSET 1 Permit Template Requirements". It contains several sections:

- Table 1:** A table with columns: Template ID, Type, Description, Tag List, Approval Route, and an "Assoc." checkbox. Rows include ILBPT1, ILB006, and ILBTMPL5.
- Checklists for Template ILBPT1:** A section with a "Checklist" table (columns: Checklist, Sequence) and an "Items for Checklist" section with checkboxes.
- Work Description for Tag List 00000000000133:** A text area for entering work descriptions.

If there are permits required for the assets, identify them in this view. Once the record is saved, you can also enter tag points and tag lists.

Asset Cost Rollup

This section provides information on the source of the data represented in SA_ASSET_COST.

Value sin the SA_ASSET_COST table reflect the Invoice amount, Timesheet amount, Service Invoice Amount, Inventory Log amount and Direct Charge amount of a particular asset under a Work Order for the particular Accounting Period.

SV_ASSET_COST

SV_ASSET_COST is the source table for the Asset module Period costs view.

Label	Field Name	Type	Desc	Source Table	Source Table Desc	Notes
Period	PERIOD_MONTH	VARCHAR2 (2)	Numeric Value of the month	SV_ASSET_COST	View	This field shows the Accounting Period that the costs shown apply to. Accounting Periods are defined in the Accounting Periods module of the Administration subsystem
	PERIOD_YEAR	VARCHAR2 (4)	Calendar Year	SV_ASSET_COST	View	
Expense Category	EXPENSE_CATEGORY	VARCHAR2 (30)	Some Period Cost views are organized by expense category	SV_ASSET_COST	View	Expense categories and codes are defined in the Expense Codes business rule.
Actual Amount	DIRECT_ACTUAL_AMOUNT	NUMBER	This column shows the actual costs for the Period.	SV_ASSET_COST	View	These amounts represent costs that have actually been invoiced and paid.

Label	Field Name	Type	Desc	Source Table	Source Table Desc	Notes
Child Amount	CHILD_ACTUAL_AMOUNT	NUMBER	This column shows the actual costs for the Period of the Child Assets	SV_ASSET_COST	View	These amounts represent costs that have actually been invoiced and paid for the Child asset.
Ext. Actual Amount	EXT_ACTUAL_AMOUNT	NUMBER	External Actual Amount	SV_ASSET_COST	View	If you have the appropriate function responsibility in your user profile, you can use these columns to compare actual amounts from an external financial system with estimates and budgets maintained by Oracle Utilities Work and Asset Management.
Ext. Child Actual Amount	EXT_CHILD_ACTUAL_AMOUNT	NUMBER	External Child Actual Amount	SV_ASSET_COST	View	
Ext. Actual Quantity	EXT_ACTUAL_QUANTITY	NUMBER	External Actual Quantity	SV_ASSET_COST	View	
Ext. Child Actual Quantity	EXT_CHILD_ACTUAL_QUANTITY	NUMBER	External Child Actual Quantity	SV_ASSET_COST	View	

SA_RULE_KEY

SA_RULE_KEY is one of the source tables for SV_ASSET_COST - Asset module Period Costs view. This is the source for the expense codes field.

FIELD NAME	TYPE	DESCRIPTION	CONSTRAINT	COMMENTS
PLANT	VARCHAR2(3)	Identifier of Organization's work site	Primary Key (PK_SA_RULE_KEY)	
RULE_ID	VARCHAR2(30)	Rule ID	Primary Key (PK_SA_RULE_KEY)	Should be "EXPENSE CODES" for Asset Period Costs
KEY_NAME	VARCHAR2(30)	Equivalent to Expense_Code of SA_ASSET_COST	Primary Key (PK_SA_RULE_KEY)	
KEY_VALUE	VARCHAR2(30)	Expense Category		

SA_ASSET_COST

SA_ASSET_COST is one of the source tables for SV_ASSET_COST - Asset module Period Costs view.

FIELD NAME	TYPE	DESCRIPTION	CONSTRAINT	COMMENTS
PLANT	VARCHAR2(3)	Identifier of Organization's work site	NOT NULL PK_SA_ASSET_COST	
ASSET_ID	VARCHAR2(15)	Unique Asset Identifier	NOT NULL PK_SA_ASSET_COST	The Asset ID is comprised of the asset record type and an ID
ASSET_RECORD_TYPE	VARCHAR2(1)	The record type has an associated list of values that is controlled by a code table.	NOT NULL PK_SA_ASSET_COST	It allows you to distinguish the kinds of Asset records you have. Some examples are: E - Equipment L - Instrumentation Loops V - Vehicle
EXPENSE_CODE	VARCHAR2(10)	Expense codes are used within the system to classify types of charges.	NOT NULL PK_SA_ASSET_COST	The actual codes are established in the Expense Codes Business Rule.
PERIOD_MONTH	VARCHAR2(2)	Numeric Value of the month	NOT NULL PK_SA_ASSET_COST	This field shows the Accounting Period that the costs shown apply to. Accounting Periods are defined in the Accounting Periods module of the Administration subsystem
PERIOD_YEAR	VARCHAR2(4)	Calendar Year	NOT NULL PK_SA_ASSET_COST	
DIRECT_ACTUAL_AMOUNT	NUMBER(15,2)	This column shows the direct actual costs for the Period		

FIELD NAME	TYPE	DESCRIPTION	CONSTRAINT	COMMENTS
CHILD_ACTUAL_AMOUNT	NUMBER(15,2)	This column shows the child actual costs for the Period		

SA_ASSET_COST

Procedures that call sdbp_cost_rollup.do_cost_rollup (WORKORDER charge type).
Sdbp_cost_rollup.do_cost_rollup inserts/updates SA_ASSET_COST.

SOURCE	PROCEDURE	BASE TABLE	MODULE
COST_INVOICE.PKB	COST_INVOICE	SA_INVOICE	Purchasing > Invoicing > Invoicing
COST_LABOR.PKB	COST_LABOR	SA_TIMESHEET	Maintenance > Employee Timekeeping > Timekeeping
COST_SERVICE_INVOICE.PKB	COST_SERVICE_INVOICE	SA_SERVICE_INVOICE_ACCOUNT	Purchasing > Service Contract > Service Invoice
COST_STOCK.PKB	COST_STOCK	SA_INVENTORY_LOG	Inventory > Checkout Transaction Log
DIRECT_CHARGES.PKB	DIRECT_CHARGES	SA_DIRECT_CHARGES	Maintenance > Employee Timekeeping > Direct Charges

SA_EXTERNAL_ACTUAL_COST

SA_EXTERNAL_ACTUAL_COST is the source table for SV_1_ASSET_COST - Asset module Period Costs view.

If users have the appropriate function responsibility in their user profile, they can use these tables to compare actual amounts and quantities from an external financial system with estimates maintained by Oracle Utilities Work and Asset Management.

FIELD NAME	TYPE	DESCRIPTION	COMMENTS
PLANT	VARCHAR2(3)	Identifier of Organization's work site	
ASSET_ID	VARCHAR2(15)	Unique Asset Identifier	The Asset ID is comprised of the asset record type and an ID
ASSET_RECORD_TYPE	VARCHAR2(1)	The record type has an associated list of values that is controlled by a code table.	It allows you to distinguish the kinds of Asset records you have. Some examples are: E - Equipment L - Instrumentation Loops V - Vehicle
PERIOD_YEAR	VARCHAR2(4)	Calendar Year	This field shows the Accounting Period that the costs shown apply to. Accounting Periods are defined in the Accounting Periods module of the Administration subsystem
PERIOD_MONTH	VARCHAR2(2)	Numeric Value of the month	
EXPENSE_CODE	VARCHAR2(10)	Expense codes are used within the system to classify types of charges.	The actual codes are established in the Expense Codes Business Rule.
EXT_ACTUAL_AMOUNT	NUMBER(15,2)	External Actual Amount	
EXT_ACTUAL_QUANTITY	NUMBER(15,2)	External Actual Quantity	
EXT_CHILD_ACTUAL_AMOUNT	NUMBER(15,2)	External Child Actual Amount	
EXT_CHILD_ACTUAL_QUANTITY	NUMBER(15,2)	External Child Actual Quantity	

Asset Activity Log Module

Use the asset activity log to record asset information independent of a work order.

Fields

Sequence No.: Asset Log ID

The record number is comprised of a unique ID. Users typically have the system generate this number.

TABLE NAME - SA_ASSET_ACTIVITY_LOG - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Create Activity Log From Asset

Grants the ability to create an asset activity log entry using the action on the Asset record.

Create Emergency Work Order Asset

Grants the ability to create an Emergency Work Order record by selecting the action on an Asset record.

Create Work Order Asset

Grants the ability to create a Work Order record by selecting the action on an Asset record.

Create Work Request Asset

Grants the ability to create a Work Request record by selecting the action on an Asset record.

Create Specification

Grants access to the action that creates a specification attachment to the current Asset record.

Charts

S_CHT148 - Planned Vs. Unplanned Downtime

A comparison of Planned Downtime to Unplanned Downtime for the current and the previous years. Downtime is considered to be “Planned” if the Downtime Scheduled indicator on the Asset Downtime record equals 'Y'. The data can be filtered by Plant. Other filtering options, including Department, Area and Asset, are available in the Chart

Field list.

Metrics

S_MTRC6 - Percent of Planned Downtime - sdbp_metric_pct_plan_outage

This metric is to describe the relationship between Planned Outage time and the total outage time as a percentage. Planned Outage time is considered an occurrence of downtime for a given Asset if the downtime was scheduled. It provides a means to monitor and improve the ratio of planned Outage time versus total Outage time

Asset Class Module

Use asset classes to group your assets, identify node types, or to create capital groups. Any classification that is created will be used on the asset record.

Define Asset Classes to group your aspects according to your organizational needs. Asset Classes should be established based on common failure characteristics and effects on the service being provided. For example, the assets listed below might be classified as indicated:

- Pumps, Filters, Instruments (Mechanical Plant)
- Sewer Pipes, Manholes, Lined Channels (Gravity Pipelines)
- Roof, Light Fittings, Floors (Buildings)
- Deck, Girders, Columns (Concrete Bridges)

Business Rules

Asset Depreciation Rule (Depreciation Parameters View)

Depreciation Rule	Value
CONVENTION	FULL-MONTH
FREQUENCY	ANNUALLY
LAST PERIOD PROCESSED	200412
LAST RUN DATE	09-FEB-05

This rule determines how the system will process asset depreciation costs and post them to the account log.

Once the values for the Convention and Frequency rule keys are set and the depreciation batch job has run, the settings should not be changed. Any modification will result in irreversible errors in your depreciation calculations.

CONVENTION - Select Full-Month to indicate the amount of depreciation that can be claimed in the year the asset is placed in service. Full-Month is the only option.

FREQUENCY - The value entered here determines how often all asset's depreciation will be written to the account log. For example, if the Last Processed Date is '200301' and the frequency is monthly, the account log will have entries of '01 2003' and in the future, the following months (i.e. 02 2003, 03 2003). Valid frequencies are Monthly, Quarterly or Annually.

LAST PERIOD PROCESSED - The Administrator should enter an initial date in this field when the rule is configured. Once the date is set the system updates the date when the account depreciation batch process runs. Do not modify this rule key after initial configuration.

The proper date format is YYYYMM.

LAST RUNTIME DATE - Last Run Date will be updated by the system whenever the batch procedure runs.

This rule allows for the creation of custom depreciation methods which can be used in place of the standard methods that are delivered with the application. Administrators can create depreciation codes here, then use the Asset Class module to enter the additional values needed to complete the calculations.

Code Tables

Code Table 107: Units (Depreciation Parameters View)

Useful Life Units field - Define valid names for the types of measurement units that can be metered and tracked to determine asset operation.

Code Table 601: Asset Class Type

Type field - Define class types.

Copy Record

ASSETCLS - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Views

Condition Assessment

Very Good (1)	Good (2)	Average (3)	Poor (4)	Very Poor (5)
100	78	59	39	19
79	60	40	20	0

Basis (Condition Assessment View)

Percentage of New

Using this basis, the condition of the asset is based on passing or failing characteristics of a new asset. A "like new" asset would pass all characteristics and be awarded the maximum points resulting in a 100% rating. A severely broken asset would fail all characteristics of a new asset and be awarded zero points resulting in a 0% rating.

The percentage ratings are translated to the 1-5 condition grade scale. A range of 100% to 80% could be equated to a Condition Grade of 1, 80% to 60% equated to a 2, and so on. The system is delivered with the default scale shown above, however

you can change the ranges when you configure each asset class record. Ranges should not overlap.

General Weighted

Using this basis, the condition of the asset is based on a general assessment of potential defects using a weighted scale of 1 - 5. Each potential defect is assigned a weight value based on the impact to service level. A potential defect that has significant impact on the service level will have a higher weight (e.g., .30) than a defect with minimal impact on the service level (e.g., .15). A “like new” asset would exhibit none of the potential defects and be awarded the minimum points resulting in a rating of 1. A severely broken asset would exhibit the highest severity of each potential defect and would be awarded the maximum points resulting in a rating of 5.

With this method the ratings are already on a scale of 1 - 5, however, fractional values might also result since fractional grades might be noted for a given condition. Therefore, the results of the General Weighted method also use a standard translation to the Condition Grade scale. For example, a range of 1 - 2 is equated to a condition grade of 1, a range of 2 - 3 equated to a condition grade of 2, and so on. The system is delivered with a default scale.

Deficiency Scoring

Using this basis, the asset condition is based on accumulated defect points. As with the General Weighted method, each potential defect is assigned a weight value based on the impact to service level. Then each defect is broken down into specific severity levels with a point value assigned to each. The more severe the nature of the defect, the higher the associated point value. Normally, the point scale is a range of 1-10, allowing for at least 10 different definitions or levels of severity.

Unlike the General Weighted method, each defect and severity identified during Inspection is accumulated for the final “deficiency score”. That is, if there are 5 defects with a severity of 2 points each, then the deficiency score for the asset would be 10. A “like new” asset would exhibit none of the potential defects and be awarded a deficiency score of 0 (i.e., absolutely no defects were noted). A severely broken asset would exhibit the highest severity of each potential defect, probably numerous times, and would be awarded a higher deficiency score.

With this method you want to set up ranges of scores that translate into the 1-5 condition grade scale. For example, a range of 0-100 could be equated to a Condition Grade of 1, 101-200 equated to a 2, and so on. The system is delivered with the default scale shown above, however you can change the ranges when you configure each asset class record. Ranges should not overlap.

Regardless of the rating basis chosen, the Only whole numbers can be entered in the limit fields. Choose the scoring basis to use for this class of assets.

Depreciation Parameters

Asset Class BYB-ASSET-CLASS-0001 Depreciation Parameters

Property Unit No.	Description
BYB-PROP-UNIT-1	BYB-ASSET-CLASS-0001 Property Unit 1 Straight Line
BYB-PROP-UNIT-2	BYB-ASSET-CLASS-0001 Property Unit 2 Double Decline
BYB-PROP-UNIT-3	BYB-ASSET-CLASS-0001 Property Unit 3 No Dep
BYB-PROP-UNIT-6	BYB-ASSET-CLASS-0001 Property Unit 6 Units of Production
DDB1	

Depreciation Parameters for Property Unit BYB-PROP-UNIT-1

Useful Life / Units: YEARS Depreciation Method:

Salvage Value:

	Accounts	Expense Codes
Asset Cost	<input type="text" value="BYB1-N-ASSET-NONE-NONE-001"/>	<input type="text" value="DEP001"/>
Depreciation Expense	<input type="text" value="BYB1-N-ASSET-NONE-NONE-002"/>	<input type="text" value="DEP002"/>
Accum Depreciation	<input type="text" value="BYB1-N-ASSET-NONE-NONE-003"/>	<input type="text" value="DEP003"/>
Disposal Gain/Loss	<input type="text" value="BYB1-N-ASSET-NONE-NONE-004"/>	<input type="text" value="DEP004"/>

Define depreciation parameters for individual property units within the asset class.

Inspection Criteria

Define the criteria and scoring that will be used to assess this class of asset.

The inspection criteria to be used when assessing assets in the given Asset Class is entered in the Inspection Criteria view. Generally, inspection criteria consists the category or high-level classifications that are weighted, and the specific characteristic or defect severity that is scored.

Asset Class STORM DRAIN Inspection Criteria

Condition Rating Basis:

Category	Weight
Debris	.3
Crack	.45
Seam	.1
Flow	.15

Total Weight:

Pass / Fail Criteria of Debris	Points
Blocked	100
Debris	80
Cluttered	60
Clear	20
Perfect	10

Each condition rating basis uses a different technique for the scoring of the assessment and therefore has slight variations on how the data is entered and displayed.

Condition Rating Basis

This non-updatable field displays the condition rating basis selected for the asset class.

Category/Defect Type

If the condition basis is Percent of New then the label for this field is Category, otherwise the label is Defect Type. This field simply represents the type or category of defect.

Weight

This field is used to indicate the rating for each deficiency entered in the Category/ Defect Type field. Values entered can not be greater than 1, and the field is limited to two decimal places. The total weight should be equal to 1 once you have entered all of the deficiencies.

Pass Fail Criteria and Points

If the condition basis is Percent of New then the labels for the fields at the bottom of the screen are Pass Fail Criteria and Points.

When configuring the inspection criteria these fields should be populated with text describing a pass/fail condition, and an assigned point value for the highlighted Category. The criteria entered here should describe characteristics of a new asset with each category broken down into the specific characteristics that a new piece of equipment would exhibit. Each characteristic should then be assigned a point value to allow for certain characteristics to contribute more than others to the cumulative point total. There can be an unlimited number of characteristics for each category.

Defect Classification and Grade

If the condition basis is General Weighted then the labels for the fields at the bottom of the screen are Defect Classification and Grade.

General Weighted: This assessment basis is similar to Deficiency Scoring in that the asset's condition is based on defects, not on characteristics of a new asset. Each Defect Type is broken down into 5 classifications each with a corresponding point value of 1 through 5. The point value of 1 usually equates to No Defects and 5 usually equates to Failed.

Users are not allowed to insert additional records or delete from the 5 records inserted by the system. The user is only able to modify the descriptive text for each attribute record.

Defect Severity and Points

If the condition basis is Deficiency Scoring then the labels for the fields at the bottom of the screen are Defect Severity and Points.

Deficiency Scoring: This assessment basis is similar to General Weighted except that each Defect Type is broken down into an unlimited number of severities each with a corresponding point value. Typically, no more than 10 severities are used and the points associated to each are 1 - 10 with 1 being the least severe condition and 10 being the most severe.

Asset Inspection Data Module

Use the Asset Inspection Data module to define Inspection criteria for your organization's assets.

Fields

Sequence No.: Inspection ID

The record number is comprised of a unique ID (Ex. "INS0000008"). Users typically select automatic generation of this number.

TABLE NAME - SA_ASSET_INSPECTION - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 23: Unit of Measure

Inspection Length and Inspection Area fields - Define codes for the weather conditions that may affect your inspections.

Code Table 181: Asset Inspection Type

Type field - Determine codes for the types of asset inspections that are done on your assets. For example, you may do visual or video inspections.

Code Table 182: Asset Inspection Reason

Reason field - Define reason codes for the asset inspections within your organization.

Code Table 183: Weather Condition

Weather Condition field - Define codes for the weather conditions that may affect your inspections.

Code Table 244: Ground Condition

Ground Condition field - Define codes for the ground conditions that may affect your inspections.

Code Table 245: Asset Inspection Severity (Observations View)

Severity Field - Define codes for the severity of your inspections.

Reports

S_RPT150 - Asset Inspection Worksheet

Lists Component ID information created in the Component ID module.

The Asset Class Inspection Criteria check boxes that appear on the report are dynamic. These are driven by the Inspection Criteria used for the Asset. To view or change this data, open the Asset Class module then open the appropriate Asset Class record. Select Condition Assessment then Inspection Criteria from the Views list on that Asset Class record. The Inspection Criteria view shows the Categories or Defects with more detailed

information located at the bottom of the screen. You can add or remove Categories or Defects in this view. The options on the report will then change accordingly.

Operational Data Module

Establish operating limits for assets and validate data against those limits in the Operational Data module. During validation, data readings that fall outside of expected limits cause alerts to be sent to the person responsible for the asset. The planner can then review the reading and, if necessary, initiate a work request to repair the measurement device or asset. The planner can then review the data and resolve the out of range condition. The Operational Data module also includes Data Import / Export Actions that enable you to import large amounts of data from external files. The Asset Data module consists of two sub-modules. The Operational Tolerance sub-module controls the data to be collected and defines the parameters under which an asset is deemed to be functioning normally, outside of which, action should be taken.

Operational Tolerance Module

Fields

Sequence No.: Operational Tolerance ID

The record number is comprised of a Measurement ID (Ex. "ILB OPTOL 1"). It is typical to have this set to be created by the user.

TABLE NAME - SA_OPERATIONAL_TOLERANCE - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 70: Measurement Type

Type field - Types define the measurement types, or the characteristics being measured, such as temperature, pressure or flow. These values are user defined and are linked to user-created Code Tables that further define these characteristics.

Copy Record

OPERTOL - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Asset Data Module

After you have established Measurement records and associated them with Asset IDs, you can use the Asset Operational Data module to record and review operational measurements for the asset. Values recorded out of the normal operating range (inner range) for the asset display an out of range indication and the system sends an alert to the alert user indicated on the Operational Tolerance record.

Business Rules

Default Directories Rule

Directory	Path
BAR CODE LABEL DROP DIRECTORY	c:\of
INSTALLED DIRECTORY	c:\sy
OPER DATA EXPORT DIRECTORY	c:\er
OPER DATA IMPORT DIRECTORY	c:\er
RFQ EXPORT DIRECTORY	c:\er
RFQ IMPORT DIRECTORY	c:\er

The Default Directories rule defines default locations for files outside of the Oracle Utilities Work and Asset Management database and is used for saving or calling files from the client computer. Individual users can establish settings in their individual User Profile record in the Administration subsystem that will supersede these business rule settings.

The Default Directories rule should not be confused with the similar Default File Locations rule, which is used to define specific file names and the paths leading to them.

Directory

BAR CODE LABEL DROP DIRECTORY - default directory to put bar code label files into.

INSTALLED DIRECTORY - directory where the application files are located.

OPER DATA EXPORT DIRECTORY - default directory for exporting Operational Data files.

OPER DATA IMPORT DIRECTORY - default directory for importing Operational Data files.

RFQ EXPORT DIRECTORY - default directory for exporting RFQ files.

RFQ IMPORT DIRECTORY - default directory for importing RFQ files.\

COMPONENT UPLOAD DIRECTORY - directory where files are stored when they are uploaded to support receiving multiple trackable components.

Path

This is the hard drive storage location for the corresponding file.

Component ID Module

Breaking down parts to the nuts and bolts level does not merit creating Component records. Instead, those types of stock items belong on a Bill of Materials (list of parts needed to maintain an item) which may in turn will be attached to Component and/or Asset records.

Fields

Sequence No.: Component ID

The record number is comprised of a unique ID (Ex. "CMP001"). Users typically allow this number to be created manually.

TABLE NAME - SA_COMPONENT_ID - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Stock Code

Since components are stock items, each Component ID requires a valid stock code. The same stock code may be referenced on other Component records, enabling the simple tracking of similar parts for swapping when failure occurs. For example, if there are two identical batteries in stock, there will be two different Component ID records, both sharing the same stock code.

Serial No.

In addition to the Component ID and the stock code, the item's Serial Number may also be entered on the Component record.

Current Location

Current Location information enables you to easily track the component. Options for Status include: Installed (Specify the Asset ID for the asset that it is installed on), In Stores (Specify the storeroom where it is located), In Repair, Inactive, Pending Disposition, Scrapped, Sold, and Outside Repair.

After a component is entered, the system maintains its status (depending on the business rule settings), setting it to one of these statuses as items are issued and returned to and from the storeroom. You can also set the status manually as appropriate.

Bill of Materials

A Bill of Materials (BOM) may be attached to the Component record. By referencing a BOM, it may be later used as a pick-list when planning parts on a related work order.

Last Install Date

The Last Install date is maintained by the system. Each time the Component ID is installed into an asset, the system updates the Last Install field with the current date.

Code Tables

Code Table 221: Component Types

Type field - Component Types classify components into groups. Classifying components in this manner facilitates searches by allowing queries to be conducted at a high level. The Results of Search completed at the Component Type level will contain valuable information that can be used to further narrow down user searches until the required component is located.

Code Table 63: Tag Types

Tag Type field (blank field next to Tagged check box) - Define the types of tags or plate names that an asset may be tagged with.

Code Table 230: Asset Record Types

The first Asset ID field - Asset Record Type categorizes the type of Asset record at a high level. Typical Asset Record Types include "E" (equipment), "I" (instrumentation), "B" (building), and "R" (room). Users can populate Code Table 230 in accordance with the logical grouping of assets that they have created in their Asset Hierarchy. This grouping serves as a method of categorizing assets and a means searching for assets.

Fleet Assets are "V" type. This value is hard coded in the system and therefore does not need to be entered.

Business Rules

Component ID Rule

The screenshot shows a configuration window titled "Business Rule COMPONENT ID RULE". It contains the following fields and sections:

- Rule ID:** COMPONENT ID RULE
- Business:** Business (dropdown)
- Parameter:** Parameter (dropdown)
- Limit?:**
- Desc:** This rule turns ON or OFF the component tracking process which allows you to track the location of any given Component ID at any given time.
- Comment:** Note: Once this Rule is turned on, users may not perform any transaction with a Component ID which affects its location without first identifying the ID number. An example would be receiving transactions for
- Table:** A table with two columns: "Component ID Processing" and "Option Status".

Component ID Processing	Option Status
COMPID_RULE	ON
- Description:** Enter ON into the "OPTION STATUS" column to enable tracking of a Component ID. Enter OFF into the "OPTION STATUS" column to prevent tracking of a Component ID.

Control component tracking. The component tracking functionality (discussed below) allows users to track the location of any given Component ID at any given time.

Functionality: Component ID is the third and final level in the Asset Hierarchy. Components are stock items such as pumps, compressors, shafts, and other items, which may be installed and de-installed into equipment. They are also defined as the major part or parts that make up an asset. Components may be interchanged with like parts (such as an old pump being replaced with a new one). Since components are stock items, each Component ID requires a valid stock code. The same stock code may be referenced on more than one Component ID record, enabling similar parts to be swapped and tracked when repair is needed or failure occurs. In order to simplify the maintenance of Components, statuses can be tracked automatically.

In order to install a Component ID on an asset the Asset ID is entered on the Component record. This action sets the Component ID status as Installed. When the same stock code


is issued (as on the Component ID record) from Stores, the system automatically de-installs the old Component ID (setting its status to Pending Disposition) and marks the issued Component ID as Installed on the asset. The status of the de-installed component must then be reviewed to decide whether to repair it, scrap it (making it inactive), or return it to stores. By default all the above functionality is configured to ON.

Configuration ID Processing and Option Status

The Component ID Rule has two states, ON and OFF. Once this Rule is turned on, users can not perform any transaction with a Component ID that affects it's location without first identifying the ID number. An example would be receiving transactions for trackable stock requires a pre-defined Component ID before the receiving transaction may be completed.

When the configuration option is set to OFF the tracking functionality of components bypassed.

Component Processing Rule



Option	Used
GET ASSET FROM COMPONENT ID	YES
GET CURRENT ASSET	YES
GET CURRENT ASSET ACCOUNT	YES
IN STORES STATUS CHANGE	YES
INSTALL AT ISSUE	NO
WORK INSTALLED W/O ASSET	YES

Description
If no asset is entered on the header, this will determine if the asset (info) that the component is installed in will be copied on header.

Determine the processing for components on work orders and PMs. The Options listed can be enabled or disabled by entering YES or NO in the Used field.

Option and Used

GET ASSET FROM COMPONENT ID - Processing for components on work orders and PMs. If this option is set to yes and no asset is entered on the header, but a Component ID is entered then the asset that the component is installed in will be copied on to the header.

GET CURRENT ASSET - Processing for Benchmarks. If this option is set to YES and no asset is entered on the Benchmark, this key determines if the asset that the component is installed in is put on the work order.

GET CURRENT ASSET ACCOUNT - Processing for Benchmarks. If no asset is entered on the benchmark, this key determines whether or not the account number for the asset that the component is installed on can be used.

INSTALL AT ISSUE - Defaulted to YES. This can only be set to NO if the Repairable Processing Rule key, Enhanced Material Disposition, is set to ON. If this option is set to NO, material disposition items will have the status of Pending Disposition when issued from the Checkout module and all status changes must be made in the Material Disposition module.

WORK INSTALLED W/O ASSET - Processing for components on work orders and work

requests. This option will allow work orders and work request to enter an installed component without entering the asset.

IN STORES STATUS CHANGE - Set this option to YES to allow the Component ID status to be changed to or from “In Stores” from the Component ID module. If this rule key is set to NO users cannot change the status to “In Stores” and they cannot remove Components from “In Stores” status. This status change does not have any impact on the On Hand quantity or the Average Unit Price in the storeroom identified on the Component ID.

Default Directories Rule

Directory	Path
BAR CODE LABEL DROP DIRECTORY	c:\of
INSTALLED DIRECTORY	c:\sy
OPER DATA EXPORT DIRECTORY	c:\er
OPER DATA IMPORT DIRECTORY	c:\er
RFQ EXPORT DIRECTORY	c:\er
RFQ IMPORT DIRECTORY	c:\er

Define default directories for use when performing client-side operations.

Directory

COMPONENT UPLOAD DIRECTORY - This is the directory where files are stored when they are uploaded to support receiving multiple trackable components. Please refer to the Component Upload section for more information on configuring this functionality.

Path

This is the hard drive storage location for the corresponding file.

Specification Upload Defaults

The screenshot shows a configuration window titled "Business Rule SPECIFICATION UPLOAD DEFAULTS". It includes a "Rule ID" field with the value "SPECIFICATION UPLOAD DEFAULTS", a "Business" dropdown, a "Parameter" dropdown, and a "Limit?" checkbox. The "Desc" field contains the text: "This rule defines default values to be used by the Component Specification Upload Wizard in the Component ID module. The wizard creates Specification records from a data upload and attaches the specifications to existing Component records. Setting the default specification type, category and description in this rule ensures that new Specification records can be created by the upload process without errors." The "Comment" field is empty. Below this is a table with columns "Column Name" and "Parameter":

Column Name	Parameter
SPECIFICATION_CATEGORY	ENV
SPECIFICATION_DESC	not used
SPECIFICATION_TYPE	ENG

The "Description" field contains the text: "The value in the Key Value column is used as the specification category when a new specification is created by the upload process."

This rule defines default values to be used by the Component Specification Upload Wizard in the Component ID module. The wizard creates Specification records from a data upload and attaches the specifications to existing Component records. Setting the default specification type, category and description in this rule ensures that new Specification records can be created by the upload process without errors.

The combination of specification type and category must match a type and category combination defined in the Specification Template module.

To use this functionality, sequence numbering for SA_SPECIFICATION_DATA and SA_COMPONENT_ID must be system generated. Open the Sequence Numbers module and make sure that there is a check in the Sys column for these tables.

Note that the SPECIFICATION_DESC parameter uses the Description as the user entered value rather than the Key Value. This is different than the other two parameters which use Key Value as the user defined string.

Web Configuration Rule

The screenshot shows a configuration window titled "Business Rule WEB CONFIGURATION". It includes a "Rule ID" field with the value "WEB CONFIGURATION", a "Business" dropdown, a "Parameter" dropdown, and a "Limit?" checkbox. The "Desc" field contains the text: "This rule defines configuration setting for the web version." The "Comment" field is empty. Below this is a table with columns "Rule", "Option", and "Setting":

Rule	Option	Setting
REPORTS ALWAYS PREVIEW	YES	
REPORTS CUSTOM VIRT DIRECTORY		http://spl-rome.us.or
REPORTS DEFAULT OUTPUT FORMAT		PDF
REPORTS OUTPUT PHYS DIRECTORY		D:\ora10gmid\Apache
REPORTS OUTPUT VIRT DIRECTORY		http://spl-rome.us.or
REPORTS SERVER NAME		repQA1715XAS

The "Description" field contains the text: "Setting this option YES forces all printing to be previewed first"

Define web configuration settings.

Rule, Option, and Setting

Enter YES or NO in the Option column for each of the rule keys. Also enter the file path or format (as appropriate) in the Setting column.

UPLOAD DIRECTORY - This is the directory where files are stored when they are uploaded to support receiving multiple trackable stock items.

Copy Record

COMPID - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Create Work Order Component

Grants the ability to create a Work Order record by selecting the action on a Component record.

Create Work Request Component

Grants the ability to create a work request by selecting the action on a Component record.

Reports

S_RPT011 - Component ID Report

Lists Component ID information created in the Component ID module.

Component Upload

Lists Component ID information created in the Component ID module.

The component upload feature requires the use of special permissions allowed through the webutils features of Oracle Forms. Configuration settings for webutils is defined in the webutil.cfg file on the Oracle Application Server. By default, security restrictions prevent files from being uploaded to the server. You must configure the webutils.cfg file to accept the upload using the following settings.

```
transfer.database.enabled=TRUE
transfer.appsrv.enabled=TRUE
transfer.appsrv.workAreaRoot=c:\temp [this must be a valid path on
the application server]
transfer.appsrv.accessControl=FALSE
transfer.appsrv.read.1=c:\temp [just have to make sure that this
is a valid path on the application server]
transfer.appsrv.write.1=c:\temp [just have to make sure that this
is a valid path on the application server]
```

An explanation of these settings can be found within the webutil.cfg file itself and within Oracle Support.

Compatible Structure Module

Compatible units can be grouped together into larger units called compatible structures. Before a compatible unit can be included on a Compatibles Structure record, it must be defined in the Compatible Unit module.

Each Compatible Structure record consists of a number of compatible units along with their associated labor and equipment estimates. Like compatible units, compatible structures can help provide consistency in the design and construction of capital projects and assist in compliance with Federal Energy Regulatory Commission (FERC) accounting and reporting requirements.

Fields

Sequence No.: Compatible Structure

The record number is comprised of a unique ID (Ex. "CS0001"). Compatible Structure numbers can be set to be system generated or created manually.

TABLE NAME - SA_COMPATIBLE_STRUCTURE- The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 23: Unit of Measure

Inspection Length and Inspection Area fields - Define codes for the weather conditions that may affect your inspections.

Code Table 225: Compatible Unit Business Unit

Business Unit field - Define the Business Unit using compatible units.

Code Table 226: Compatible Unit Class

Class field - Code table linked to the Business Unit.

Code Table 227: Compatible Unit Equipment Group

Equipment Group field - Code table linked to the Class.

Copy Record

COMPSTRU

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Update Active CU/CS

Allows users to update active compatible units or compatible structures.

Compatible Unit Module

Compatible units provide consistency in the design and construction of capital projects. Compatible units may also assist in compliance with Federal Energy Regulatory Commission (FERC) accounting and reporting requirements.

To fully configure compatible unit functionality the following steps must be completed:

1. Set compatible units business rules, code tables and functions as outlined in these chapters.
Compatible Unit Module
Compatible Structure Module
Regulatory Account Module
Work Order Task Module
2. Define stock items as CU materials by selecting the Reconcile to CU check box on the stock item if applicable.
3. Set up regulatory accounts. Please refer to the Regulatory Account chapter in the Compatible Units User Guide for more information.
4. Define compatible units with the appropriate functions, difficulties, usage codes, asset classes, and property units referenced. Please refer to the Compatible Units chapter in the Compatible Units User Guide for more information.
5. Define compatible structures. Please refer to the Compatible Structures chapter in the Compatible Units User Guide for more information.

When testing configuration settings, please follow the completion guidelines for work order tasks to see how costs are applied and posted for compatible units.

Fields

Sequence No.: Compatible Unit ID

The record number is comprised of a unique ID (Ex. "CU0001"). Compatible Unit IDs can be set to be system generated or created manually.

TABLE NAME - SA_COMPATIBLE_UNIT- The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 22: Vendor Characteristic Types (Characteristics View in Vendor module)

Contractor field - Define contractors which can be added on in the Compatible Units Contractor Bids view. The values are carried over when the compatible unit is referenced on work records.

Code Table 23: Unit of Measure

Inspection Length and Inspection Area fields - Define codes for the weather conditions that may affect your inspections.

Code Table 224: Compatible Unit Difficulty (Functions View)

Difficulty field - Define degrees of difficulty for functions. You can use the Difficulty and Function fields together to define several degrees of difficulty for the same function, for example, a normal installation and a difficult installation, but each function/difficulty combination must be unique. The list of values associated with the Difficulty field displays only selections that have not yet been associated with the Function for this Compatible Unit record.

Code Table 225: Compatible Unit Business Unit

Business Unit field - Define business units according to your organizational practices. Code table 226 is linked to this table to define classes. Other linked tables can be created to further define other business units. For example, create a code for Water, then link another table to define types of water such as “above ground” or “under ground.”

Code Table 226: Compatible Unit Class

Class field - Code table linked to the Business Unit.

Code Table 227: Compatible Unit Equipment Group

Equipment Group field - Code table linked to the Class.

Code Table 1197: Compatible Unit Type

CU Type field - Define type codes for compatible units.

Business Rules

Compatible Unit Defaults Rule

The screenshot shows a configuration window titled "Business Rule COMPATIBLE UNIT DEFAULTS". It contains the following fields and table:

- Rule ID: COMPATIBLE UNIT DEFAULTS
- Business: Business
- Parameter: Parameter
- Limit?:
- Desc: Defaults for Compatible Units
- Comment: (empty)
- Table with columns Key Name and Values:

Key Name	Values
CONTRACTOR EXPENSE CODE	00014
CRAFT	ELEC
CREW SIZE	2
EQUIPMENT QUANTITY	1
EQUIPMENT TYPE	TRUCK
STOREROOM	CUS

Description: Contractor Expense Code

The Compatible Unit Defaults Rule sets the default values for estimating equipment and labor rates for compatible units. When a new is inserted, the system uses the values from this rule to populate the Equipment view and to calculate duration, equipment and labor estimates.

CONTRACTOR EXPENSE CODE - This sets the default expense code that is charged when contractor costs are applied from a work order. Contractors are entered in the Contractor Supplied view in the Work Order Task module.

CRAFT - When compatible unit is entered on the CU Worksheet, the system automatically creates an entry on the Items Worksheet for every compatible unit, plus a line for labor estimates. The craft entered in the Value field here will be defaulted on the Items Worksheet for the labor estimates. The craft can be changed later on the worksheet, if necessary.

CREW SIZE -The crew size used to estimate duration (duration = manhours/crew size).

EQUIPMENT QUANTITY - The quantity used to estimate default equipment cost (cost = rate x quantity).

EQUIPMENT TYPE - Select an Equipment Type from the list of values controlled by the Other Direct Charges business rule. You can enter any Equipment Type. If a default Equipment Type is defined here, the system inserts a line with that type into each new Equipment view. Any additional equipment that you add to the Compatible Units record must be defined in the Direct Charges Rule with a Units value of Hour or Hourly.

STOREROOM - The storeroom used when materials from a CU are added to the Work Order Task Item Worksheet. If the stock item does not exist in this default storeroom, the system searches for the stock item in all other active storerooms. If the stock item is found in another storeroom, the system uses that storeroom. If the stock item is found in more than one storeroom, the system does not enter a value but informs you that some material items on the Item Worksheet do not include a valid storeroom. You must then open the Item Worksheet and select a storeroom from the list of values.

Compatible Unit Function Rule

The screenshot shows a configuration window titled "Business Rule COMPATIBLE UNIT FUNCTION". It includes fields for Rule ID (COMPATIBLE UNIT FUNCTION), Business (Business), List, and Limit?. The Description field contains: "This rule is used to associate whether work done on a compatible unit is categorized as new, retire or existing depending on the function." The Comment field contains: "Enter a function and type to categorize a compatible unit with that function as new, retire, or existing for the CU Summary view in Work Design." Below these fields is a table with two columns: Function and Type.

Function	Type
CODE 1	Existing
CODE 2	Existing
INSTALL	New
REMOVE	Retire
RETIRE	Retire
ROTATE	Existing
TRANSFER	Existing

At the bottom, there is a Description field with the text "Synergen Default Code".

This rule is used to associate whether work done on a compatible unit is categorized as a new, retire or existing construction asset depending on the function.

Enter a function and type to categorize a compatible unit with that function as new, retire, or existing for the CU Summary view in Work Design.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Copy to New Compatible Unit

Allows the user to create an exact copy of an existing Compatible Unit record.

Show CU Location

Allows users to access the CU Location and Location Worksheet views on Work Order Tasks. Users must also have the SHOW CU ON WO responsibility. When this function is not present the compatible units location views do not display in the Work Order module.

Show CU on Work Order

Grants access to compatible units views on Work Order records. Note that this is the function that controls whether compatible units is turned "on" or "off." When this function is not present the compatible units views do not display in the Work Order module.

Replace CU Material Item

Grants access to the action in the Compatible Units module that makes global updates to compatible units material items. For example, if item1 needs to be replaced by item2, the action finds all compatible unit and Work records that reference item 1 and replaces it with item 2.

Update Active CU/CS

Allows users to update active compatible units or compatible structures.

Reports

S_RPT151 - Compatible Units Audit Report

Lists compatible units and their stock code, function, equipment, labor and account attributes.

Views

Accounting

Usage Code	Description	Property Unit No	Capital	Maintenance	Operations
DO	Distribution Overhead		<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
SL	Street Lighting		<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
TO	Transmission Overhead		<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
XO	Line Transformer Overhead		<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>	<input type="checkbox"/>
			<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
			<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
			<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

The Accounting view provides a way of associating compatible units with Usage Codes and other indicators for accounting purposes.

Usage codes are defined in the Regulatory Account Usage Codes Business Rule.

Functions

Function	Difficulty	Manhours	Standard Price	Salvage Price	Include Material
INSTALL	DIFFICULT	11.00	1,000.00	200.00	<input checked="" type="checkbox"/>
INSTALL	NORMAL	8.00	750.00	200.00	<input checked="" type="checkbox"/>
REMOVE	NORMAL	6.00	700.00	200.00	<input checked="" type="checkbox"/>
TRANSFER	NORMAL	7.00	3.00	200.00	<input checked="" type="checkbox"/>
					<input type="checkbox"/>
					<input type="checkbox"/>

Estimates

Labor	\$269.50
Equipment	\$550.00
Material	\$470.23
Total	\$1,289.73

Business Rule Defaults

Craft	ELEC
Crew Size	2

The Functions view contains descriptions of planned activities defined for the compatible unit and an estimate of the costs involved.

Header (Master Catalog module)

Any stock item that will be added to compatible units materials lists must be configured to work as a CU material item.

Stock Type - The item should be an Inventory type stock item.


Status - The item must be in Active status to be used as a compatible unit material.

Reconcile to CU - Check this box if the item should be tracked for Work Order Task CU Reconciliation. If the box is checked and more or less of the planned quantity is used for work, the item must be reconciled.

When a CU is reconciled on the Work Order Task, the Regulatory Account Costs are deleted from the CU Reconciliation view and the costs are redistributed to the new Regulatory Account splits created from the reconciliation process the next time sdbp_regulatory_account_cost or run all batch is run. These splits are shown in the Regulatory Accounting view on the Work Order Task.

Conductor Information view (Master Catalog module)

The conductor information view is used to define a stock item as a conductor for use with compatible units.



The information entered in this screen defines the parameters for determining additional conductor length for slack based on the distance between two attachment points. The CU quantity and items quantity is automatically calculated for the stock item using the distance entered on work documents (Work Designs and Work Order CU Location) and the information entered here. Please note that slack is not factored into the calculation if the Underground check box is checked when the item is added to the CU Location (Detail) view on the work record.

From and To represent the starting and ending point values of the stock code length to apply the calculation to based on the "Distance" defined on the work document. The Multiplier and Adder represent a number to be multiplied and added to the stock code length that falls on or between the From and To values.

Please refer to the User Guide topic, Compatible Units for Conductors, for more information.

Bill of Materials Module

The system allows for the creation of maintenance Bills of Materials in support of Material and Service Requirements functionality on work orders and benchmark work orders. The Bill of Material module enables the user(s) to maintain a listing of commonly used parts needed for asset maintenance.

Fields

Sequence No.: BOM ID

The record number is comprised of a unique ID (Ex. "RLW_BOM001"). Bill of Material record numbers are typically set to be created manually.

TABLE NAME - SA_BOM_DATA - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Breakdown Indicator

When you initially open the record, the Bill of Materials list shown is for the top level of the list. The Breakdown For field indicates this by showing the same number as shown in the BOM ID field at the top of the window. However, each of these parts may have a lower sub-list of parts. For example an engine can consist of valves, pistons, etc. all with parts lists of their own. You can access the sub-lists (if any) by clicking the V buttons at the start of each line in the list. Return to the top level by clicking the TOP Level button. If a further breakdown exists for a BOM item, the V button will appear bold.

Caution: The system will not prevent you from listing a part on its own sub-list. In other words, the same part can be used on both the parent and child levels. Doing so, however, is illogical and will cause the system to behave erratically when you attempt to display the sub-level breakdown.

Code Tables

Code Table 29: Asset Types

Asset Type field - Classify assets into defined groups. Classifying assets in this manner facilitates searches by allowing queries to be conducted at a high level. The Results of Search completed at the Asset Type level will contain valuable information that can be used to further narrow down user searches until the required Asset record is located. This code table is configured under the following modules: Procedure, Asset, BOM.

Copy Record

BOMDATA - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Update BOM

Grants access to an action that allows users to delete or replace a stock item from all Bill of Materials records that currently list the stock item.

Batch Processes

Create BOM Details - `sdbp_create_bom_details.create_bom_details`;

Provides an automated means of updating existing bill of materials with new stock codes based on other operations occurring in the system. Stock Code is added to the BOM ID related to Asset ID/Component ID information selected from SA_INVENTORY_LOG and SA_RECEIVING_LOG tables. Once a log record is successfully processed, it is marked as complete.

Reports

S_RPT081 - Bill of Material Report

Lists Bill of Material information created in the Bill of Material module of the Resource subsystem.

Change Request Module

Fields

Sequence No.: Change Request No.

The record number is comprised of a unique ID (Ex. "0200015"). Change Request record numbers are typically set to be system generated.

TABLE NAME - SA_CHANGE_REQUEST - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Next Approver Field

Designate approvers for Change Requests in the Approval Limits module of the Administration subsystem under Approvals and Routes.

Code Tables

Code Table 136: Create New Asset Transaction Types

Transaction Type field on Asset Change (New) view - Classify and group change requests.

Code Table 141: Change Asset Information Transaction Types

Transaction Type field on Asset Change (Change) view - Classify and group change requests.

Code Table 162: Dispose of Asset Transaction Types

Transaction Type field on Asset Change (Dispose) view - Classify and group change requests.

Code Table 163: Change Asset Configuration Transaction Types

Transaction Type field on Asset Change (Configure) view - Classify and group change requests.

Code Table 165: Change Request Types

Type field - Use type codes to classify and group Change Requests.

Code Table 166: Change Request Classes

Class field - Use class codes to further categorize and group Change Requests.

Code Table 167: Impact Types

Impact field - Impact codes can be defined in any way that fits your business practices. Two possible examples are by the relative impact (high, moderate, low, etc.), or the type of impact (process shut down, plant shut down, etc.).

Code Table 168: Justification Types

Justification field - Justification codes can be defined in any way that fits your business practices. A typical example would be a code indicating the reason the change is required (i.e. OSHA regulations).

These fields contain a general code, but users can enter a more detailed impact or justification for the change in the text field to the right of the fields in the module.

Business Rules

Change Request Record Types Rule

The screenshot shows a configuration window titled "Business Rule CHANGE REQUEST RECORD TYPES". It includes fields for Rule ID, Desc, and Comment. Below these are two tables: "Record Type" and "Option", and two columns for "Header Frozen" and "Notes Frozen".

Record Type	Option	Header Frozen	Notes Frozen
ASSET	ON	COMPLETED	COMPLETED
CATALOG	ON	APPROVED	COMPLETED
GENERIC	ON	APPROVED	COMPLETED
STOREROOM	ON	APPROVED	COMPLETED
VENDOR	ON	APPROVED	COMPLETED

Description: This rule determines the Change Request record type as ASSET

Define which record types are managed in the Change Request module, and when modifications on these records are “frozen.”

Record Type and Option

ASSET - When value is ON, you can create Change Requests for Asset records. When value is OFF, you can not create this type of Change Request.

CATALOG - When value is ON, you can create Change Requests for Master Catalog records. When value is OFF, you can not create this type of Change Request. Default is OFF.

GENERIC - When value is ON, you can create Generic Change Requests . When value is OFF, you can not create this type of Change Request.

STOREROOM - When value is ON, you can create Change Requests for Storeroom records. When value is OFF, you can not create this type of Change Request. Default is OFF.

VENDOR - When value is ON, you can create Change Requests for Vendor records. When value is OFF, you can not create this type of Change Request.

Header Frozen, Note Frozen

For each record type, select the record status that the record is in when changes can no longer be made to the header or notes.

Work Order Processing Rule

WO Processing Rule	Document	Status	Value
▲ ALLOCATE COSTS TO ASSETS		OFF	APPROVED
APPLY CHANGE REQ CREATED FR WO		ON	
AUTO ADD DEPENDENT MATERIALS		ON	
AUTO CLOSE CHECKOUT REQUESTS		ON	
AUTO UPDATE TRAVEL TRIPS		ON	
BUYER CODE	REQUISITION		GST
CHANGE REQUEST ENFORCEMENT		ON	
CHECK OPEN MATERIAL RECORDS		ON	
COPY EMERGENCY WO TO SCHEDULE	DAILY	ON	NEXT
DELAY CONSTRUCTION ASSET VALUE		ON	
DIRECT PURCHASE	REQUISITION	PENDING APPROVAL	
DIRECT PURCHASE BLANKET		ON	
▼ DIRECT PURCHASE DUTY TAX			0

Description
Set this rule key to ON to have the system reverse asset costs on work order tasks and distribute the costs across assets on the asset list by creating adjustment records. The status of the resulting Cost Adjustment record will be the status entered in the Value column. Change CPE4750 if you have business processes that do not require...

Controls the work order processes specified in the WO Processing Rule column.

WO Processing Rule, Document, Status and Value

APPLY CHANGE REQ CREATED FR WO - This rule key determines whether change requests for construction assets will be applied automatically when created from work orders. If the rule key status is set to ON, the system creates Change Request records based on entries made to the Construction Asset view on the Task and sets those Change Requests to 'Complete' status. The requested changes are automatically posted to the assets. If the rule key status is set to OFF the Change Requests are created and set to 'Created' status so that they must be reviewed before any change is made to the assets. Whether the rule key setting is YES or NO, the 'sdbp_create_change_req.create_change_from_wo' batch process is triggered once the Task status is set to 'Finished' and the Work Order status is set to 'Closed'.

DELAY CONSTRUCTION ASSET VALUE - This rule key determines when construction assets are valued for depreciation. If it is set to OFF then Construction Assets are valued the first time sdbp_work_order.fixed_asset is run after the Work Order is set to Closed status. If it is set to ON then construction assets are not valued until after sdbp_year_end_oh_cost_dist (Indirect Overhead) is run based on the schedule established by the INDIRECT OVERHEAD ALLOCATIONS rule key of the Regulatory Account Options business rule.

Copy Record

CHNGREQ - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or

action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Change Request Actions for AVL

Grants the ability to access and use the Actions for Vendor type Change Requests.

Change Request Asset

Grants the ability to apply the approved changes from an Asset type change request.

Change Request Catalog/Storeroom

Grants access to items on the Actions lists for Catalog and Storeroom type Change Requests.

Reports

S_RPT114 - Change Request Report

Lists the Assets, Components, Analysis, Notes, Work Requests, Work Orders, Tasks, and attachments pertaining to Change Requests.

Employee Module

Fields

Sequence No.: Employee No.

The record number is comprised of a unique ID (Ex. "0003"). Employee record numbers are typically set to be system generated.

TABLE NAME - SA_EMPLOYEE - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Department and Area

Use these fields to assign an employee to a specific Department and Area within your organization. These fields are controlled by the Department and Area modules.

Auto-Timesheet Schedule Fields

Complete the fields in the Auto-Timesheet Schedule View to set-up automatic timesheet creation for users. If an employee routinely works a fixed schedule and charges time against the same charge numbers, the system can be configured to automatically create timesheets for that employee.

When the relevant information is entered on the Auto Timesheet Schedule view and the Automatically Create Timesheet box is checked, batch processing creates timesheets for each workday within the pay period and alerts the employee when the timesheet for the pay period is created.

Business Rules

Craft Rates Rule

The screenshot shows the 'Business Rule CRAFT RATES' configuration window. It includes fields for Rule ID (CRAFT RATES), Business (Business), List, and Limit?. The Description is 'This rule is used to define the craft standard rate and expense codes.' The Comment is 'The first column is the type of "Craft", which can be no longer than five (5) characters. The second column is the "Rate". The third column is the "Regular Expense" code. The fourth column is the "Premium'.

Craft	Rate	Reg Expense	Prem Expense
ADMN	25	00003	00004
APPRN	17.5	00003	00004
CARP	20	00003	00004
CUST	18.50	00003	00004
ELEC	24.50	00003	00004

Description: Admin

Define Craft codes along with associated wage rates and expense codes.

Craft

Classify job types in the Craft field. Examples are ENG for engineer or MECH for mechanic.

Rate

This parameter sets the wage rate for the Craft listed.

Reg Expense

This parameter sets the expense code that the system will charge the employee's regular (i.e. non-premium) labor charges to.

Prem Expense

This parameter sets the expense code that the system will charge the employee's premium (i.e. Overtime) labor charges to.

Scheduled Holidays

The screenshot shows the 'Business Rule SCHEDULED HOLIDAYS' configuration window. It includes fields for Rule ID (SCHEDULED HOLIDAYS), Configuration, List, and Limit?. The Description is 'This rule is used to define Holidays for a Calendar Year(s) to be used for the creation of Timesheets for Employees flagged as "Automatically Create Timesheet". If an automatic timesheet Employee is scheduled'. The Comment is 'The format of the date should be entered as "MMDD/YYYY".'

Holiday	Date	Charge Type	Charge Number	Ex
2ND HOLIDAY	03/11/2004	V	001	OC
ANOTHER HOLIDAY	03/23/2004	C	003X	OC
NEXT HOLIDAY	03/25/2004	H	TIMESHT	OC

Description:

The Scheduled Holidays rule defines holidays the system uses when creating timesheets for employees flagged for automatic timesheet creation.

If an employee is scheduled to work on the same day as a scheduled holiday, the Timesheet line item will be created using the Charge Type, Account and Regular Expense Code defined for the holiday. Shift and Differential information will come from the appropriate Employee record.

Timekeeping Authority Rule

Username	Authority	Org Level	Override
63NEWUSER	SUPERVISOR		
FINE GRAIN CONTROL 1	SUPERVISOR		
FRED	SUPERUSER		
GUEST	SUPERVISOR		
IBROWN	SUPERVISOR	TITLE	
JCOOL	PAYROLL		

Use this rule to define which users can access and maintain timesheets, leave requests, and employee records. This rule only controls who has access to the records, approval authorization is controlled in the Approval Limits module.

Note: A supervisor defined in this module does NOT correspond to the Supervisor fields defined by code table 310.

Username

Enter individual Usernames to set an authority level for access to Employee records, Timesheets, and Leave Requests. Anyone not listed will have the DEFAULT authority. By setting the USERNAME column to DEFAULT and the AUTHORITY column to EMPLOYEE, all users will be granted employee level authority without your needing to identify them explicitly.

Authority

The Authority column defines the scope of a users' authority. The authority levels include: Employee, Supervisor, Superuser and Payroll.

EMPLOYEE - User can only view or modify their own timesheet or employee record. Org Level does not apply.

SUPERVISOR - User can view or modify their own records and records of members of the Org Level entered. The Org Level value is used to widen the scope of the Supervisor authority. Set the value to Department, Area, or Crew, and the system limits the corresponding username to have access to other user's records who share the same Department, Area or Crew on their EMPLOYEE record. If you enter TITLE as the Org Level, the username is limited to see the user's records who are on the same CREW module record with the username. This allows Supervisors to approve timesheets for multiple crews (any crew that they are on).

SUPERUSER - User can view or modify any record. Org Level does not apply.

PAYROLL - User can view or modify any record, as well as override or adjust Compensatory Time Accrual calculations. Org Level does not apply.

For example, If BIGBOSS is entered under username in this business rule with the Authority set to Supervisor, and the Org Level set to Title, the system provides him access to the records for all users who are on the same CREW module records as BIGBOSS. If the Org Level is left blank or set to Crew the system provides BIGBOSS with access to the records of every user who has the same Crew entered on their EMPLOYEE module record as he has on his Employee record.

Org Level

The Org Level value is used to widen or narrow the scope of the Supervisor authority. See above for valid values and definitions.

Override

The override value is only used for those with the Supervisor or Superuser authority to temporarily promote them to Superuser or Payroll authority. Enter Superuser or Payroll in the Override column to give this authority to a user (to substitute for a supervisor who is on vacation, for instance). Filling in this value does not modify the authority of any other user. It can be changed or cleared later to restore the user to their original authority.

Batch Processes

Auto Create Timesheets - `sdbp_auto_create_timesheet.main`;

Triggers functionality where the system automatically creates timesheet records for employees as designated on their Employee record. The system can be configured to automatically create timesheets for employees who work a fixed schedule by checking the Automatically Create Timesheet? Indicator in the Auto Timesheet Schedule view in the Employee module.

Code Tables

Code Table 45: Training Courses (Training View)

Course field - Define course codes. The Course Code can be up to 20 characters long, and the Description field can be used for longer descriptions.

This is a non-validating code table. If there are additional courses to be added, they can be typed into the Course field and the system saves them to the SA_Employee_Training folder, but does not write the value back to Code Table 45. This is why you can have more choices available in the List of Values than shows on the Code Table 45 record.

Code Table 46: Payroll Group

Pay Group field - Categorize employees by how they are paid. Entries might include Part Time, Full Time, Hourly, Salaried, etc.

Code Table 48: Leave Reason Codes (Scheduled Leave View)

Reason column - Define leave reason codes. Examples might include Maternity, Sick, Vacation, etc.

Code Table 98: Administrative Department

Admin Dept. field - Define employee's assigned departments. Some examples may be 'ENG', 'HR', 'FIN', etc. Classifying employees to their respective departments serves as a useful means of searching for employees where the department is known.

Code Table 99: Classification

Classification field - Classify employees. Typical examples may include classifications based on union contracts, management structure, etc.

Code Table 111: Overtime Crew (Overtime Standings View)

Crew field - Determine in what crew a particular employee is available for overtime work.

This information can be used on the search options screen to help in finding employees.

Code Table 112: Overtime Zone (Overtime Standings View)

Zone field - Determine in what Zone a particular employee is available in for overtime work. This information can be used on the search options screen to help in finding employees available for Overtime work in a particular zone.

Code Table 208: Employee Job Title

Job Title field - Define employee job titles. The 'Code' column has a maximum data length of 6 characters. The 'Code Desc' column can be used for a longer description.

Code Table 310: Supervisor Title

Supervisor field - Define supervisory positions. These codes do not identify individuals. Some examples include Plant Superintendent, Electrical-Shift 1 Supervisor, or Foreman.

Copy Record

EMPLOYEE - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Employee SSN

Grants access to the employee Social Security Number displayed in the Employee module.

Employee Wage Rate

Grants access to the employee Wage Rate information displayed in the Employee module.

Reports

S_RPT012 - Employee Report

Lists Employee information created in the Employee module of the Resource subsystem.

S_RPT078 - Holiday Overtime Standing Report

Provides a listing of Employees for holiday call-in overtime.

S_RPT061 - Wage Rate History Report

Lists Employee Wage Rate information from the Wage Rate History detail in the Employee module of the Resource subsystem.

Attachments Modules

There are seven Attachments modules in the system: Document Control, Procedure, Specification, Specification Template, Standard Notes, MSDS, and Chemical Label.

Business Rules

Attachment Print Configuration Rule

Key Name	Option Status	Paths
GHOSTSCRIPT APPLICATION	OFF	C:\GS
GHOSTSCRIPT PARAMETERS	OFF	-dNO
PRINT ATTACHMENTS TO PRINTER	ON	Wspl-
REPCACHE UNC PATH	OFF	

This rule controls whether attachments are sent directly to a printer when the Print action is selected in the Work Order, Work Order Task, Fleet Work Order, or one of the Benchmark modules.

Any user that will use this functionality MUST have the printer that they plan to print to installed on their computer.

PRINT ATTACHMENTS TO PRINTER - Set this value to ON to send Work Order attachments directly to the printer when the Print action is selected in a module. The default is set to OFF. You must also make sure that the REPORTS ALWAYS PREVIEW rule key in the Web Configuration business rule is set to OFF. This value is also available in the User Profile. the value setting in the User Profile will override the business rule setting.

The attachment must be in .pdf format and a third-party application called Ghostscript must be installed on the application server and must be configured properly.

REPCACHE UNC PATH - This is the output directory path for reports on the application server. This path must be in UNC format only: \\<SERVER_NAME>\REPCACHE\
. Example: \\paris\repcache\

GHOSTSCRIPT APPLICATION - Path and file name of the Ghostscript executable. Depending on the version of the installed Ghostscript product, these values could vary. Example: C:\gs\gs.exe

GHOSTSCRIPT PARAMETERS - These parameters are used by the Ghostscript program to disable interactive prompting. There is also another parameter, -sDEVICE, which is appended to this string by the application. This parameter is populated by the GS Device rule key in the PRINTER ALIAS Business Rule. Example: -dNOPAUSE -dBATC

Attachment Drive Mapping Rule

The screenshot shows the configuration window for the 'Business Rule ATTACHMENT DRIVE MAPPING'. The Rule ID is 'ATTACHMENT DRIVE MAPPING', the category is 'Business', and the list type is 'List'. The description is 'This rule is for Attachment drive mapping.' The comment field is empty. The 'Drive Map' section contains a list of drive letters: G, O, P, V, W. The 'Machine Name' section contains a list of machine names: W10.138.131.95\attac, W\walnutcreek\dept, W10.138.131.97\attac, W10.138.131.105\use, and W\ball'synergen\qa171. The description field contains 'Rome Attachments.'

Use this rule to map drives where attachment files are stored.

Enter a drive and the machine the drive should be mapped to in the appropriate columns. Attachments stored on these drives and attached to applicable records will be converted to the UNC path when printed.

For Blanket Contracts and Purchase Order records this setting affects e-mails with attachments sent from the record where the E-Mail Purchase Order action is selected and the Print indicator is checked.

Attachment Types Rule

The screenshot shows the configuration window for the 'Business Rule ATTACHMENT TYPES'. The Rule ID is 'ATTACHMENT TYPES', the category is 'Business', and the parameter type is 'Parameter'. The description is 'This rule determines what attachments are allowed.' The comment is 'The first column is the "Attachment Type", the second is to ALLOW or DISALLOW. The description is used to populate the item list for the attachment.' The 'Attachment Type' section contains a list of attachment types: DOCUMENT, MSDS, PROCEDURE, SPECIFICATION, STANDARD NOTE. The 'Option Status' section contains a list of option statuses: ALLOW, ALLOW, ALLOW, ALLOW, ALLOW. The description field contains 'Document'.

Determine which attachment types are made available as Attachments throughout the application (such as in the Asset, Storeroom, Catalog, Work Order and Process modules).

Attachment Type and Option Status

Standard attachment types include Document, MSDS, Chemical Label, Procedure, Specification, and Standard Notes. Set the Option Status field to ALLOW or DISALLOW to enable or disable the attachment. You can also add additional attachment types if needed.

Document Storage Types

Storage Type	Option Status	Option Usage
EXTERNAL	ON	DEFAULT
INTERNAL	ON	

Description
File System

This rule determines the available storage types in the Create Document Record wizard. This rule affects all modules that allow the user to add a document as an attachment using the Create Document Record wizard, for e.g. Asset, Storeroom, Work Request, Change Request modules.

STORAGE TYPE- Storage Type of EXTERNAL indicates that files can be stored in a file system. Storage Type of INTERNAL indicates that files can only be stored within Oracle Utilities Work and Asset Management.

OPTION STATUS - For each Storage Type, set the Option Status to either ON or OFF to determine whether the storage type is available for use within the system.

OPTION USAGE- Use the Option Usage setting to determine which Storage Type is the default value in the Create Document Record wizard.

The list of values for the Stored In field of the Create Document wizard is populated with the storage types that are set to ON in this business rule.

Printer Alias Rule

Name	Actual Name	Short Desc.
1000HP8000N	WUSA11000HP8000N	
685HP8KN ON TOPAZ	WTOPAZ1685hp8KN	
850HP8KN ON TOPAZ	WTOPAZ1685hp8150N	
CLOSEST	WTOPAZ1600hp5si	
FRIENDLY NAME	Technical Name	
MAIN PRINTER	Wusa11000HP8150MF	

Description

Indicate the printer names and destination names to be used to print within the system. The printer alias, as defined in the NAME column, will populate the Printer field on the user's User Profile record as default information. This printer will override the user's PC

default printer.

NAME - The name field establishes an “alias,” or user-friendly name for the printer indicated in the Actual Name column. This value will populate the Printer field on the User Profile record as the default (up to 30 characters).

ACTUAL NAME - Enter into the “ACTUAL NAME” column the printer name that a specific operating system would recognize (up to 30 characters).

If you have many different operating systems (i.e. Windows95, WindowsNT, etc.) printing to one printer, the printer name is stored in the “ACTUAL NAME” column. This printer name can be found in the Control Panel for the operating system under Printers.

You must enter the printer name in the following format: \\<server name>\<actual printer name> (e.g. \\MYSERVER\685HP8KN if “685HP8KN” is the actual printer name), OTHERWISE THE PRINTER WILL NOT BE RECOGNIZED. If the printer name changes, you only need to change the Business Rule setting, not all of the User Profile records.

SHORT DESC. - Enter into the “SHORT DESC.” column a description of the printer (up to 30 characters).

GS DEVICE - If the PRINT ATTACHMENTS TO PRINTER rule key in the ATTACHMENT PRINT CONFIGURATION Business Rule is set to ON, enter into the “GS Device” column the Ghostscript device name that applies to the printer. An example of this would be “LASERJET” for an HP LaserJet printer. The printer entered must be the correct name and it must be supported by the installed version of Ghostscript. To find a valid list of printer device names, please refer to your Ghostscript documentation.

Web Configuration Rule

Rule	Option	Setting
REPORTS ALWAYS PREVIEW	YES	
REPORTS CUSTOM VIRT DIRECTORY		http://spl-rome.us.ora
REPORTS DEFAULT OUTPUT FORMAT		PDF
REPORTS OUTPUT PHYS DIRECTORY		D:\ora10gmid\Apache
REPORTS OUTPUT VIRT DIRECTORY		http://spl-rome.us.ora
REPORTS SERVER NAME		repQA1715XAS

Description
Setting this option YES forces all printing to be previewed first

Define web configuration settings.

Rule, Option, and Setting

Enter YES or NO in the Option column for each of the rule keys. Also enter the file path or format (as appropriate) in the Setting column.

REPORTS ALWAYS PREVIEW - Setting this option YES forces all printing to be previewed first.

REPORTS BARCODE FONT - Enter a value in the setting field to specify the font to be used on reports that include a barcode field. The font that is entered should be available in your system fonts. You can find fonts by searching the internet for “Free Barcode Fonts.”

REPORTS CUSTOM VIRT DIRECTORY - This is the web server virtual directory to run the Oracle Reports CGI program for the web version.

REPORTS DEFAULT OUTPUT FORMAT - Default Report Output File Format.

REPORTS OUTPUT PHYS DIRECTORY - This is the web server physical directory to put report output for the web version.

To enable e-mailing of Purchase Orders to Vendors, allow network access to the directory defined under this rule key. Once this access is allowed, identify this network share in the E-Mail Configuration Business Rule under the key PO EMAIL FILE LOCATION.

REPORTS OUTPUT VIRT DIRECTORY - This is the web server virtual directory to retrieve report output for the web version.

REPORTS SERVER NAME - This is the name of the reports server for the web version.

UPLOAD DIRECTORY - This is the directory where files are stored when they are uploaded to support receiving multiple trackable stock items.

Printing PDF Attachments

This document describes how to configure Oracle Utilities Work and Asset Management to send PDF attachments directly to printer, rather than having them display on the screen, when a record is printed with attachments.

Checklist

The printing attachments functionality requires the following components:

1. Oracle Utilities Work and Asset Management V1.7.15 or greater
2. Ghostscript (a freeware program – AFPL Ghostscript is recommended)

Installation

Obtain Ghostscript

A freeware version of AFPL Ghostscript is available on the Internet at several locations. One location where you can find Ghostscript is: <http://pages.cs.wisc.edu/~ghost/doc/AFPL/index.htm> For a Windows based server, it is recommended that you download the “.exe (32-bit Windows)” version. For Ghostscript version 8.54, the file is named gs854w32.exe.

NOTE: This functionality was tested using Ghostscript version 8.54. Earlier versions may yield unexpected results.

Install Ghostscript

It is recommended that you install Ghostscript in a directory that does NOT have spaces in the path name. If the on-screen installation instructions prompt that you install in C:\Program Files, it is recommended that you choose another directory with no spaces in the path name. To install, launch the installation executable program and follow the installation instructions.

Business Rule Settings for Ghostscript

Four business rules need to be set in the Oracle Utilities Work and Asset Management application in order for the Ghostscript integration to work correctly.

Attachment Print Configuration Rule

Examples of Key settings

Key Name	Status	Paths/Params	Notes
GHOSTSCRIPT APPLICATION		C:\GS\gs8.54\bin\gswin32c.exe	This is an example. Enter the exact path/and file name for your Ghostscript executable.
GHOSTSCRIPT PARAMETERS		-dNOPAUSE -dBATCH	Do NOT alter these parameters unless you are familiar with Ghostscript.
PRINT ATTACHMENTS TO PRINTER	ON		This value needs to be set to ON in order to enable this functionality.
REPCACHE UNC PATH		\\<server>\repcache	This is the output directory path for reports on the application server. This path must be in UNC format only.

Attachment Drive Mapping Rule

This business rule is used to map network drive letters to UNC paths. Enter a drive letter and the UNC path of the server\directory that it should be mapped to, in the appropriate columns.

Printer Alias Rule

This business rule that has a new column titled “GS Device” (Ghostscript Device).

Examples of Key settings:

Name	Actual Name	Short Desc.	GS Device
COPY ROOM PRINTER	\\MYSERVER\G3242P		laserjet
FLOOR 2 PRINTER	\\MYSERVER\G3146MFP		pxlmono

The GS device name you enter must be correct for your printer and must be supported by the installed version of Ghostscript.

To find the correct GS device for your printer, see the Printers section of the following website: <http://www.gnu.org/software/ghostscript/devices.html> Another website containing GS device names for a large number of printers is: http://openprinting.org/printer_list.cgi

Find a list of Ghostscript devices supported by the installed version of Ghostscript:

1. **Open a command prompt.**
2. **Navigate to the “bin” directory where Ghostscript was installed, example: C:\Ghostscript854\gs8.54\bin.**
3. **Launch the executable with “-h” after it, example: gswin32c -h**

This returns a variety of information, including a list of available devices. The device you enter in the Printer Alias business rule must be on this list. There may also be documentation included with your installed version of the Ghostscript application.

NOTE: Some generic settings you can try for HP or Epson printers (and they may work for other laser printers as well) are:

HP Laserjet - "laserjet"

Epson black and white printers - "pxlmono"

Web Configuration Rule

The Web Configuration Business Rule has a setting called REPORTS ALWAYS PREVIEW. When REPORTS ALWAYS PREVIEW is set to YES, reports and attachments will be displayed in a window on the client PC. If it is set to NO and the report is defaulted with a Destination of Printer (in Report Administration), then the report and its PDF attachment(s) will print directly to the printer.

IMPORTANT: This setting is also available as an option in the User Profile module. If a REPORTS ALWAYS PREVIEW value is set in the User Profile, that value will override the value set in the Business Rule.

Troubleshooting

Error Messages

Below is a list of the more common error messages that may appear when printing attachments, together with the possible cause and suggested corrective action.

- Getting Repcache path from ATTACHMENT PRINT CONFIGURATION > REPCACHE UNC PATH B.R. key
Cause: The ATTACHMENT PRINT CONFIGURATION > REPCACHE UNC PATH rule key may be missing.
Action: Verify that this value exists and add the value if missing.
- Verify the following file exists: <path\filename.ps>
Cause 1: The ATTACHMENT PRINT CONFIGURATION > REPCACHE UNC PATH rule key is incorrect or misspelled.
Action 1: Verify that this value is correct and is not misspelled. Correct as needed.
Cause 2: In the ATTACHMENT PRINT CONFIGURATION rule, the printer the user is attempting to print to may contain a misspelled GS Device value. Also, the device may not be supported by the version of Ghostscript installed on the application server. Please refer to the "Ghostscript Devices" section in this guide for instructions on obtaining a list of supported printers.
Action 2: Verify that this value is valid and is not misspelled. Correct as needed.
- Verifying the following file is greater than 0 bytes: <path\filename.ps>
Cause 1: The user may not have access/security privileges to the Repcache directory.
Action 1: Verify that the user has access/security privileges to the Repcache directory. On the user's PC, open Windows File Explorer and try to access the Repcache directory by entering the path in the Address Bar. If a logon screen appears, the user should logon to the server and try printing attachments again.
Cause 2: The user may not have access/security privileges to the network directory where the PDF attachment is located.

Action 2: Verify that the user has access/security privileges to the network directory where the PDF attachment is located. On the user's PC, open Windows File Explorer and try to access the network directory where the attachment is located by entering the path in the Address Bar. If a logon screen appears, the user should logon to the server and try printing attachments again.

Cause 3: The network drive may not be mapped on the application server.

Action 3: On the application server, the network drive may not be mapped to the server. Also, see the "Limitations" section regarding attachments on a network drive.

Cause 4: The drive letter in the ATTACHMENT DRIVE MAPPING Rule may have an invalid Machine Name value.

Action 4: Verify that this value is correct and is not misspelled. Correct as needed.

- Mapping network drive letter to machine name - Unable to locate drive mapping in ATTACHMENT DRIVE MAPPING B.R.

Cause: In the ATTACHMENT DRIVE MAPPING Rule, the mapped drive, for which the attachment is located, may not have a Machine Name value or the rule key for the relevant mapped drive may not exist.

Action: Verify that the drive mapping exists in the Rule and that the Machine Name value isn't missing.

- Getting Ghostscript application path and executable from ATTACHMENT PRINT CONFIGURATION -> GHOSTSCRIPT APPLICATION B.R. key

Cause: The ATTACHMENT PRINT CONFIGURATION > GHOSTSCRIPT APPLICATION rule key may be missing.

Action: Verify that this value exists and add the value if missing.

- Verifying existence of Ghostscript application in the following location: <path>\ghostscript executable>

Cause: The ATTACHMENT PRINT CONFIGURATION > GHOSTSCRIPT APPLICATION rule key is incorrect or misspelled.

Action: Verify that this value is correct and is not misspelled. Correct as needed.

- Setting -sDEVICE parameter for printer device

Cause: In the ATTACHMENT PRINT CONFIGURATION Rule, the printer, for which the user is attempting to print to, may not have a GS Device value or the rule key for the printer may not exist.

Action: Verify that the printer exists in the Rule and that the GS Device value isn't missing.

- Calling sdbp_call_url stored procedure

Cause: In the SA_INTERNET_INTEGRATION table, the value of the SIA_URL may be incorrect. This value should match the SIA address in which the user is signed into. An example of this would be: http://spl-paris.us.oracle.com:1715/synergen/

Action: Verify that the SIA_URL is correct. NOTE: If there are multiple records in this table, the record with the most current TIMESTAMP value is used.

SA_REPORT_QUEUE Table

The SA_REPORT_QUEUE database table is also helpful for troubleshooting print attachment failures. Records created in this table by the print attachment functionality have a value of 'ATTACHMENT' in the OS_MODE field.

SA_REPORT_QUEUE Columns and their meanings, for attachments sent directly to printer.

Column Name	Values or Meaning
PLANT	The Plant of the user who submitted the report.
REPORT_ID	The report number for which the attachment is associated with.
REPORT_SEQ_NO	System generated sequence number.
REPORT_STATUSES	Possible statuses and their meanings: Queued: The application attempted to generate the attachment but failed in the process before the Java Printing program was called. JavaPrint processing: The error occurred during the call to the Java Printing program. Failed: The error occurred in the Java Printing program. Completed Date/Time: The print process completed successfully (the report was successfully submitted to the printer, but not necessarily printed by the printer).
DESTYPE	This will always say "Printer".
DESNAME	The name of the printer to which the attachment was sent.
DESFORMAT	This will always say "PS" (Postscript).
RUN_DATE	System date when the record was inserted.
WHERE_CLAUSE	The location and name of the PDF file that was submitted for printing. For BLOB attachments, the location will be the Repcache directory where the BLOB was extracted.
ORDER_BY	The location and the name of the Postscript file that was generated by the Ghostscript application. The Java Print program will send this file to the printer.
SUBMITTED_BY	The user who submitted the report.
SUBMITTED_DATE	System date when the record was inserted.
OS_MODE	This will always say "ATTACHMENT".
COPIES	This should always be NULL.

NOTE: If the print attachment functionality errors out early in the process, there may be no record in this table because the database will rollback the insert.

Limitations

The following are known limitations of the Print PDF Attachments Directly to Printer functionality.

- This functionality works only with PDF format attachments.
- This functionality is available only in the following modules:
 - Work Order (WORKORD)
 - Work Order Task (WOTASK)
 - Benchmark Work Order (BENCHWO)
 - Fleet Work Order (FLEETWO)
 - Fleet Bench Work Order (BENCHFLT)
- This functionality is not available from Scheduling modules at this time.
- This functionality may not work correctly in a multiple Oracle Utilities Work and Asset Management application server environment.
- Local attachments (C: drive attachments, etc.) do not print.
- Attachments with HTTP:// type file paths are not supported at this time.
- Landscape attachments do not print correctly.
- When using the Print WO w/Documents Action, the attachments will most likely print BEFORE the Work Order report because the attachments printing process is faster than the Oracle Reports printing process.
- The Printer must support Postscript printing.
- Some printers may not be supported by the Ghostscript application.
- The printer the user is printing to must be installed on the application server, where the Oracle Utilities Work and Asset Management application is running.
- Users may or may not be able to print attachments that are located on network drive that is different than the network drive on which the Oracle Utilities Work and Asset Management application is running, because of network security settings and other factors.

IMPORTANT: Because of possible network security issues, it is highly recommended that you test printing attachments located on separate network drives, if you plan to allow users to print attachments that are not on the same network drive as the application server or are not stored in the database as BLOBs. If you do encounter difficulties printing to other drives, it is recommended that you create an Attachments directory on the server where the Oracle Utilities Work and Asset Management application is running.

Document Control Module

The Document Control module allows you to enter and maintain the location of external attachments to the system.

Fields

Sequence No.: Document ID

The record number is comprised of a unique ID (Ex. "ILB0002"). Document Control record numbers are typically set to be created manually.

TABLE NAME - SA_DOCUMENT - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 409: Document Classifications Codes

Type Codes field - Define document types. Typical entries might be Text for text documents, Drawing for CAD files, WO for work order related documents, etc.

Code Table 276: Document Media Types

Media field - Define document formats. Possible document formats might be Microfiche, Electronic, Paper, etc.

Code Table 410: Document File Types

File Type field - File Types are identified by the 3-character extension that accompanies the file name. Typical entries include 'CAD', 'BMP', 'DOC', 'XLS', etc.

Copy Record

DOCUMENT - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Document to Active

Determines which users can activate document records that have the Revision Handling check box checked. Records that do not have this check box checked are not affected by this function.

MSDS Module

Manage material data safety sheets in the MSDS module.

Copy Record

MSDS - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Chemical Label Module

The List of Values for the Chemical Label List in the MSDS module is controlled by entries in the Chemical labels module. Enter a Chemical Label name, a Description, and the TDG Product name (if applicable) in the fields provided.

Copy Record

MSDSCHEM - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Specification Module

Use Specifications to develop detailed descriptions of requirements, dimensions, materials, and so on. Specifications can vary in type from Engineering to Service History to Accounting to just about anything that you need to define.

Reports

S_RPT005 - Specification Report

Lists specifications and attributes created in the Specification module of the Resource subsystem.

Specification Template Module

Fields

Sequence No.: Specification ID

The record number is comprised of a unique ID (Ex. "CAK-SPEC-2"). Specification record numbers are typically set to be created manually.

TABLE NAME - SA_SPECIFICATION_DATA -The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 37: Specification Types

Type field - Categorize specifications for searching purposes. Typical Specification types might be Build for building specs, Eng for engineering specs, Chem for chemical specs, etc.

Linked Code Table (i.e.101): Specification Category Codes

The Code Tables linked to Code Table 37 entries are used as the default, all Specification Types in Code Table 37 are linked to Code Table to provide another level of specification grouping for searching purposes. If a Specification Type in Code Table 37 does not contain a Link to another code table, the user may enter anything into the Category field for that Spec Type. You may establish unique Specification Categories for each Specification Type by inserting a new code table and associating it to a Spec Type with the Link field in Code Table 37.

Views

Specification Configuration



The screenshot shows a window titled "Spec Template SERV_HIST Category GEAR Configuration". It contains a table with the following columns: "Seq No.", "List of Values", "Code Table", and "Query". The first row is populated with the value "1" in the "Seq No." column and "USE_QUERY_KEY_VALUE" in the "List of Values" column. The "Code Table" and "Query" columns are currently empty. There are four empty rows below the first one, each with a small downward arrow on the right side of the "List of Values" column.

Seq No.	List of Values	Code Table	Query
1	USE_QUERY_KEY_VALUE		

This view appears on the Views list when you select one of the Attributes fields on the Specification Template header.

Select Configuration from the Views list to define the List of Values type that should be used to populate the Specification Value field in the Specification module. You can select a List of Values based on a Code Table or a list based on an entered query. If you select a query type, a query must be entered in the Query field. A List of Values type is not required. If no List of Values is chosen, user's can enter any value in the Specification Value field of the Specification record. The chosen List of Values can also be overridden on Specification records created from a template that uses the List of Values.

Seq No.

This Sequence Number corresponds to the Sequence number of the Attribute on the Specification Template record that will be controlled by this List of Values.

List of Values

You can choose to use a List of Values that is based on either a Code Table that exists in the system or on a custom query entered in the Query field.

Code Table

If you choose CODE_TABLE_KEY_VALUE in the List of Values field, select the Code Table that you want to use in this field.

Query

If you choose USE_QUERY_KEY_VALUE enter the custom query text in this field.

Standard Notes Module

Enter and maintain a set of standard notes in the Standard Notes module.

Fields

Sequence No.: Standard Notes ID

The record number is comprised of a unique ID (Ex. "ILB01"). Standard Notes record numbers are typically set to be created manually.

TABLE NAME - SA_STANDARD_NOTES - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 91: Standard Note Types

Type field - Categorize standard notes for searching purposes. Typical standard note types might be Buyer, Invoice, Safety, etc.

Copy Record

STDNOTES - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Procedure Module

Maintain lists of step-by-step directions.

Fields

Sequence No.: Procedure No.

The record number is comprised of a unique ID (Ex. "ILB03"). Procedure record numbers are typically set to be created manually.

TABLE NAME - SA_PROCEDURES - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 16: Procedure Types

Type field - Categorize the types of procedures at a high level. Typical Procedure Types include Electrical, Lubrication, Safety, etc. You can also search by Procedure Types.

Code Table 28: Procedure Categories

Category field - Another way to categorize procedures. Procedure Categories might include Calibration, Gaging, Bushings, etc. You can also search by Procedure Categories.

Code Table 29: Asset Type

Asset Type field - Classify assets into defined groups. Classifying assets in this manner facilitates searches by allowing queries to be conducted at a high level. The Results of Search completed at the Asset Type level will contain valuable information that can be used to further narrow down user searches until the required Asset record is located. This code table is configured under the following modules: Procedure, Asset, BOM.

Business Rules

Procedure Attachment Update

The screenshot shows a configuration window for a business rule. The title bar reads 'Business Rule PROCEDURE ATTACHMENT UPDATE'. The 'Rule ID' is 'PROCEDURE ATTACHMENT UPDATE', the 'Business' is 'Business', and there are 'Parameter' and 'Limit?' checkboxes. The 'Desc' field contains: 'This rule is used to define which attachment tables are updated when a new revision of a procedure is created in the Procedure module. When the option is set to YES the system updates the procedure on that...'. The 'Comment' field contains: 'The sample query below is for the table name SA_ASSET_PERMIT_ATTACHMENT. It sets the rule key so that the revision update is made in the Asset Permit Attachments view (SA_ASSET_PERMIT_ATTACHMENT) when the asset record (SA_ASSET) is in any status other than...'. Below this is a table with columns 'Table Name', 'Option Status', and 'Subquery'. The 'Table Name' column lists various attachment tables, and the 'Option Status' column has 'YES' for all. The 'Subquery' column is empty for most rows, but contains 'and (plant, asset_rec...' for SA_ASSET_PERMIT_ATTACHMENT. At the bottom, there is a 'Description' text area.

Table Name	Option Status	Subquery
SA_ACTIVITY_ATTACHMENT	YES	
SA_ADJUSTMENT_ATTACHMENT	YES	
SA_ASSET_ACT_ATTACHMENT	YES	
SA_ASSET_ATTACHMENT	YES	
SA_ASSET_CLASS_ATTACHMENT	YES	
SA_ASSET_INSPECTION_ATTACHMENT	YES	
SA_ASSET_PERMIT_ATTACHMENT	YES	and (plant, asset_rec...
SA_BLANKET_CONTRACT_ATTACHMENT	YES	
SA_BLANKET_ITEM_ATTACHMENT	YES	
SA_CATALOG_ATTACHMENT	YES	
SA_CHANGE_ITEM_ATTACHMENT	YES	
SA_CHANGE_ORDER_ATTACHMENT	YES	
SA_CHANGE_REQUEST_ATTACHMENT	YES	

This rule is used to define which attachment tables are updated when a new revision of a procedure is created in the Procedure module. When the option is set to YES the system updates the procedure on that attachment table. When the option is set to NO, the system does not update the procedure and the older revision remains on the attachment table. Enter an SQL query in the Subquery column to set additional parameters. For example, you can restrict processing to only update the attachment table when the header is in a certain status.

The sample query below is for the table name SA_ASSET_PERMIT_ATTACHMENT. It sets the rule key so that the revision update is made in the Asset Permit Attachments view (SA_ASSET_PERMIT_ATTACHMENT) when the asset record (SA_ASSET) is in any status other than “Retired.”

```
and (plant, asset_record_type, asset_id) in (select plant, asset_record_type, asset_id from sa_asset t where a.plant = t.plant and a.asset_record_type = t.asset_record_type and a.asset_id = t.asset_id and t.asset_status != 'RETIRED')
```

Procedures Authority Rule

Username	Type	Activate
AUTOMATION	ALL	
FRED	ALL	
HUTSON	ALL	
JGEE	ALL	
NEW 012	MECHANICAL	
NEWGUY2002	MECHANICAL	

Determine which users can create or update Procedure Step records based on a Procedure Type. Basic authority to Display, Select, Insert, Update and Delete Procedure records require the configuration of the PROCEDURES module in the responsibility matrix.

Username

Enter the username with the authority to update Procedure records. If a user's username is not listed the system refers to the authority for the Username DEFAULT for that person.

Type

Enter the Procedure record type that the user has authority over in the Type field next to Username.

To grant a user authority across all or none of the Procedure Types, enter ALL or NONE, respectively. If the username DEFAULT does not exist, users who are not listed in the Rule have a default authority type of NONE.

Activate

Enter Allow in the Activate column for if the user has authority to activate a procedure (DISALLOW [or blank] or ALLOW). Disallow/Blank is the default.

Copy Record

PROCEDUR - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Add/Delete Job Hazard

Grants the ability to access the Add/Delete Job Hazard action in the Procedure module.

Create New Procedure Revision

Grants access to the Create New Revision action in the Procedure module.

Modify Job Hazard

Grants the ability to access the Modify Job Hazard action in the Procedure module.

Reports**S_RPT003 - Procedures Report**

Lists the Procedures created in the Procedures module of the Resource subsystem.

Job Hazard Module

Fields

Sequence No.: Hazard ID

The record number is comprised of a unique ID (Ex. "JH0001"). Job Hazard record numbers are typically set to be created manually.

TABLE NAME - SA_JOB_HAZARD - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 470: Job Hazard Type

Type field - Categorize the types of hazards at a high level.

Code Table 471: Job Hazard CategorY

Category field - Secondary level of hazard categorization.

Code Table 472: Protective Equipment

Protective Equipment field - Identify equipment that can be used to control potential hazards.

Copy Record

JOBHZRD - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Revise Procedure

Grants the ability to access the Revise Procedure action in the Job Hazard module.

Function Module

The Function module can be used to capture non-work order or non-purchasing costs such as Safety Meetings, Snow Removal and so on. Unlike a Process record, a Function record stands alone and does not receive cost-rollups from other modules.

Fields

Sequence No.: Function ID

The record number is comprised of a unique ID (Ex. "F FN001"). Function record numbers are typically set to be created manually.

TABLE NAME - FUNCTION - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 137: Function Types

Type field - Classify your organization's functions. Populate this code table in accordance with the logical grouping of functions that have been created in your Asset Hierarchy. As well as being an important means of categorizing functions it also facilitates user searches by being a selection criteria.

Code Table 110: Backlog Group

Backlog Group field - These groups can be used to group crews or to find and categorize work orders at a high level. This code table is used in the Process, Asset, Function, Work Request, Work Order, and Crew Activity Log modules.

Copy Record

FUNCTION - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Process Module

The Process module enables you to enter and maintain information pertaining to a work process rather than to a specific asset. A Process is considered a group of assets that together perform a work process. Process can be considered the top level of the Asset Hierarchy in so far as cost association. The Maintenance Manager module looks at cost buckets in a similar fashion.

Fields

Maintenance Manager Field

The Maintenance Manager field on the Process header screen can be populated with a code that represents an additional cost rollup path that can be used with assets. Create and modify Maintenance Manager codes in the Maintenance Manager module. Use of Maintenance Managers can cause the grouping of costs for a set of related, or unrelated, assets. The cost rollup to the Maintenance Manager is independent of the Asset Hierarchy cost rollup path, which is the primary benefit of this feature. As the title suggests, this can be an individual who is charged with monitoring costs for a type of asset. For example, a performance engineer may wish to monitor activities related to pumps (e.g., maintenance history, costs, runtime data). Adding a unique code under Maintenance Manager to each of the pumps for which the performance engineer is responsible will provide a means of tracking costs for all these pumps, as well as providing a mechanism of quickly sorting these pumps from the asset listing.

Planner Field

The List of Values for this field is controlled by the values set in the Planner Business Rule.

Maintenance and Production Approver Fields

Maintenance and Production Approvers are defined in the Approval Limit module. The Approval type must be set to M or B for the approval title to show up on the lists of values for these fields in the Process module. If these approval titles are included in the Work Order Defaults view of an asset they are copied to the Additional Data views on work requests and work orders where that asset is referenced. Planners can open the Additional Data view and review this information to decide which Next Approver to enter on the header record.

Department, Area, and Account Fields

When entering default Account information, the List of Values for Account Number is controlled by the entered Department and Area. Only those Account Numbers with matching Department / Area values (including no Department / Area) are valid.

Fixed Asset Field

If there is a Fixed Asset to be associated with the process, enter it in this field.

Code Tables

Code Table 138: Process Types

Process Type field - Populate Code Table 138 according to the grouping of processes that have been established for your asset hierarchy. As well as being an important means of categorizing Processes, Process Type can also be used as selection criteria on the Search Options screen.

Code Table 25: Building Codes

Building field - Define building identifiers for the asset location specific to your organization.

Code Table 110: Backlog Groups

Backlog Group field - These groups can be used to group crews or to find and categorize work orders at a high level. This code table is used in the Process, Asset, Function, Work

Request, Work Order, and Crew Activity Log modules.

Code Table 231: Location

Location field - Define codes for asset locations specific to the client organization. The Location field is searchable from the Search Options screen.

Business Rules

Planner Rule

Code	Full Name	Username
123456	Max Length	BYB_USER_1
BYB1	Branwen Y. Burgess	BRANWEN
RLW	Ray Winther	RAY
RYM	Raya Veksler	RVEKSLER
SRP	sudha's	SREDDY
WWW	Nolan and Lauren's D	WILLLY

Define planner codes, and identify the full names and usernames associated to each code. These codes are used when identifying a planner on work records.

The user associated with the code receives an alert when an event occurs where an alert would be sent to the planner. For example, when a planner plans parts against a work order and needs to be notified when the parts have arrived. This does not mean that the system is configured to send alerts regarding any record where a planner is indicated.

Code

Enter the codes for planners in the Code column. Each code must be unique.

Full Name

Enter the full name of the person associated with the code. A person can be listed on more than one code.

Username

Enter the username of the person associated with the code. Since a person can be listed on more than one code, the username can be listed more than once as well.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Create Work Order Process

Grants the ability to create a work order by selecting the action on a Process record.

Create Work Request Process

Grants the ability to create a work request by selecting the action on a Process record.

Copy Record**PROCESS - COPY RECORD**

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Reports**S_RPT006 - Process Report**

Lists the processes created in the Process module of the Resource subsystem.

S_RPT007 - Process Report with Asset Detail

Lists the processes created in the Process module of the Resource subsystem along with a breakdown of the assets attached.

Maintenance Manager Module

Several modules reference a Maintenance Manager field. Codes for this field are created and managed in the Maintenance Manager Module.

In the Process modules this code can represent an additional cost rollup path that can be used with assets. Use of Maintenance Managers can cause the grouping of costs for a set of related, or unrelated, assets. The cost rollup to the Maintenance Manager is independent of the Asset Hierarchy cost rollup path, which is the primary benefit of this feature. As the title suggests, this can be an individual who is charged with monitoring costs for a type of asset. For example, a performance engineer may wish to monitor activities related to pumps (e.g., maintenance history, costs, runtime data). Adding a unique code under Maintenance Manager to each of the pumps for which the performance engineer is responsible will provide a means of tracking costs for all these pumps, as well as providing a mechanism of quickly sorting these pumps from the asset listing.

Copy Record

MAINTMGR - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Keys and Locks Module

Code Tables

Code Table 515: Set Category (User)

Type field - Define codes to further define key and lock categories.

Maintenance Subsystem

Work Request Module

Fields

Sequence No.: Work Request No.

The record number is comprised of a unique ID (Ex. "0100051"). Work record numbers are typically set to be system generated. Setting them to be user created is not recommended.

TABLE NAME - SA_WORK_REQUEST - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Approval Route Field

Designate approvers for work requests in the Approval Limit module under Approvals and Routes in the Administration subsystem.

Business Rules

Batch Purge Criteria Rule

Batch Processing	Status 1	Status 2	Status 3	Status 4
▲ EVENT QUEUE STATUSES	FAILED	FAILED		
REQUISITION PO STATUSES	CLOSED	CANCELED		
WORK REQUEST WO STATUSES	CLOSED	CANCELED	REJECTED	HISTORY
▼				

Define the status values which determine when to delete obsolete data. Records are deleted when batch purge processing runs. Enter the applicable statuses in the Status 1, Status 2, and Status 3 columns for each record type. For example, for work requests, if the value in the Status 1 column is set to CLOSED, the system purges any work requests associated to work orders in CLOSED status.

Batch Processing

EVENT QUEUE STATUSES - Delete event queue entries that are in the statuses identified in the status columns.

REQUISITION PO STATUSES - Delete requisitions associated with purchase orders in the statuses identified in the status columns. Typically, Requisitions are considered unnecessary after the PO has been CLOSED or CANCELED.

WORK REQUEST WO STATUSES - Delete work requests associated to work orders that are in the statuses identified in the status columns. Recommended options for Status 1 - 4 include work orders in CLOSED, CANCELED, HISTORY, or REJECTED status. Although it is possible, it is NOT recommended that you purge work requests associated to work orders in PLANNING, PENDING APPROVAL, APPROVED, ACTIVE or FINISHED status.

STATUS 1, STATUS 2, STATUS 3 - These columns indicate the statuses for the records that are purged. Status 1 is the prime status to be deleted. Status 2 and 3 are other desired statuses.

Batch Purge Parameters Rule

Batch Parameters	Days
ALERTS	1
AUDIT LOG	0
BATCH_MESSAGES	7
EVENT QUEUE	5
REQUISITIONS	9
WORK REQUESTS	0

As system data ages, it often becomes of little or no value to users. Purging old data regularly prevents tables from growing too large and helps maintain a quick system response time when querying those tables.

The Batch Purge Parameters Rule defines, per specific type of data, the age of a record before batch processes purges it. Note that the specific routines called for purging are already defined, purging either a single record at a time or a header record and its associated view, whichever is appropriate.

Batch Parameters and Days

ALERTS - Set the number of days the system should retain Alerts on the home page. Purge processing compares the Alert Date to the current date minus the number of days listed in the DAYS column, and deletes any messages that fall outside of that range.

AUDIT LOG - Set the number of days the system should retain Audit Log entries. Purge processing compares the date that the entry was made to the current date minus the number of days listed in the DAYS column, and deletes any messages that fall outside of that range.

BATCH_MESSAGES - Messages generated by batch processing and are stored as records in the Job Manager module so that you can easily access and review them at any time. Purge processing compares the Batch Message Date to the current date minus the number of days listed in the DAYS column, and deletes any messages that fall outside of that range.

REQUISITIONS - Purge Processing compares the PO Status Date (for status settings in the Batch Purge Criteria business rule) to the current date. When the result is greater than the number of days listed in the DAYS column, the Requisition is deleted from the system.

WORK REQUESTS - Purge Processing compares the Work Order Status Date (for status settings in the Batch Purge Criteria business rule) to the current date. When the result is greater than the number of days listed in the DAYS column, the work request is deleted from the system.

Criticality Override Rule

Business Rule CRITICALITY OVERRIDE

Rule ID: Business Limit?

Desc: This rule allows the criticality field (selected from the Asset module) to be modified when copied to a Work Order or a Work Request. Such processing is appropriate when Asset records do not have the correct

Comment: Default processing is DISALLOW.

Module	Option Status
WORK ORDER	ALLOW
WORK REQUEST	ALLOW

Description: The criticality field is not available for update in the Work Order and Work Order Task modules.

Control modification of the Criticality field on Work Order and Work Request records. The Criticality field is defined on the Asset record then copied onto work records when an asset is referenced. Set the option status to Allow or Disallow to control whether or not the field can be modified. Allowing modification is appropriate if your Asset records generally have no criticality or an incorrect criticality assigned to them.

The Criticality field is the first Priority field on work records. The default is to DISALLOW if the field is left blank.

Default Backlog Groups Rule

Business Rule DEFAULT BACKLOG GROUPS

Rule ID: Business Limit?

Desc: This rule allows a user to build a relationship between a crew and a backlog group.

Comment: The following modules are affected by this Business Rule:
Work Request, Work Order, Work Order Task, Benchmark Work Order and PM Master (detail - Additional

Crew	Backlog Group
BYB	BYBBLG
CAK1	CAKBLG
DP1	DEPOT1
GE	CAKBLG
LAB	BYBBLG
MASON	DEPOT1
RJB	RJBBLG
RVM	RVMBLG

Description:

The Default Backlog Group business rule allows a user to build a relationship between a crew and a backlog group for Work Requests, Work Order Tasks, Benchmark Work Order Tasks, PM Masters, and schedules.

An example of how the concept of a backlog crew may be used is that Crew A (Crew) works 1st shift and Crew B (Backlog Group) works 2nd or 3rd shift and takes on any unfinished tasks originally scheduled for Crew A (Crew) on 1st shift.

Crew and Backlog Group

Enter valid Crew codes (Code Table 15) in the Crew column. In the Backlog Group column enter Backlog Group codes (Code Table 110) associated with the Crew.

Default Work Request Req Date Rule

The screenshot shows a configuration window titled "Business Rule DEFAULT WORK REQUEST REQ DATE". It includes fields for Rule ID, Desc, and Comment. Below these is a table with three columns: "WO Priority Range From", "To", and "Days". The table contains the following data:

WO Priority Range From	To	Days
0	25	14
26	39	10
40	60	7
61	79	3
80	99	1

Below the table is a "Description" field with the text: "The range from-to must be from 0 to 99. In the second and subsequent rows, the 'from' should be the previous 'to' + 1".

Establishes the work order priority range and the number of days to be added to the system date, to create a default required date for a work request. If the total priority is blank the system interprets a 0 value for the total priority.

WO Priority Range From / To

Define the Work Order Priority ranges. The overall range must cover 0-99. In the second and subsequent rows the FROM value should be the previous row's TO value plus 1.

Days

Determine the number of days to be added to the system date for each Priority range.

Planner Rule

Code	Full Name	Username
123456	Max Length	BYB_USER_1
BYB1	Branwen Y. Burgess	BRANWEN
RLW	Ray Winther	RAY
RVM	Raya Veksler	RVEKSLER
SRP	sudha's	SREDDY
WWW	Nolan and Lauren's D	WILLY

Define planner codes, and identify the full names and usernames associated to each code. These codes are used when identifying a planner on work records.

The user associated with the code receives an alert when an event occurs where an alert would be sent to the planner. For example, when a planner plans parts against a work order and needs to be notified when the parts have arrived. This does not mean that the system is configured to send alerts regarding any record where a planner is indicated.

Code

Enter the codes for planners in the Code column. Each code must be unique.

Full Name

Enter the full name of the person associated with the code. A person can be listed on more than one code.

Username

Enter the username of the person associated with the code. Since a person can be listed on more than one code, the username can be listed more than once as well.

Work Request Authority Rule

Business Rule WORK REQUEST AUTHORITY

Rule ID: WORK REQUEST AUTHORITY Business List Limit?

Desc: This rule dictates (1) usernames; (2) the types of Work Orders from Work Requests; (3) the status the Work Order will be created in; (4) whether or not they may actually create the Work Order; (5) which

Comment: The 1st column is the "USER NAME". The 2nd column defines the created Work Order types (REGULAR [default], URGENT or EMERGENCY). The 3rd column defines the initial Work Order status authority

Username	Type	Authorization	Action	Op
BRANWEN	EMERGENCY	ACTIVE	CREATE	Off
PETERPAN	REGULAR	PLANNING	CREATE	Off
RAY	EMERGENCY	ACTIVE	CREATE	Off
RBEELER	EMERGENCY	ACTIVE	CREATE	Off
RVEKSLER	EMERGENCY	ACTIVE	CREATE	Off
WILLY	EMERGENCY	ACTIVE	CREATE	Off

Description:

Determines the users that can create work orders from work requests and the conditions associated with creating those work orders.

Username

Enter the names of the users who have the authority to create work orders from work requests. Since the values entered for DEFAULT will apply all users that are not specifically listed, make sure that the values entered for DEFAULT are set according to the authority you want to give unlisted users.

Type

Defines the type of work order created from a work request. The values are REGULAR (default), URGENT, or EMERGENCY. Users granted EMERGENCY can also enter URGENT and REGULAR. Users granted URGENT can also enter REGULAR.

Authorization

This column determines what status will be assigned to a work order created by that particular user. The values are PLANNING (default), APPROVED or ACTIVE.

Action

Activates or deactivates the user's ability to create a work order from a work request. Options are:

CREATE - allow users to generate work orders from work requests.

NOCREATE - (default) prevents the user from generating work orders from work requests.

Option

Set Option to ON or OFF depending on whether or not you want to allow the user to be able to add to existing work orders from work requests. The default is OFF.


Status

Defines the work order status that a work request can be added to --(PLANNING [default], APPROVED or ACTIVE).

Delete if WO

Determines whether or not the user can delete work requests if there is a work order associated with it. DISALLOW is the default.

Work Request Processing Rule



Business Rule WORK REQUEST PROCESSING

Rule ID: Business Parameter Limit?

Desc:

Comment:

WR Processing Rule	Status
CHANGE REQUEST ENFORCEMENT	ON
DEFAULT ROUTE FROM ACCOUNT	ON
DEFAULT ROUTE FROM ASSET	ON

Description:

Establish whether or not the system checks for a change request before allowing a status change on a work request. Also set default Approval Titles and choose whether you want the default to come from the Account or Asset record associated to the request. If the Approval Route field is empty when a work request in CREATED status is saved, the system will populate the field with the Approver designated in the rule.

WR Processing Rule, Status, and Type

CHANGE REQUEST ENFORCEMENT - If this rule key is set to ON and the initial work order status is set to ACTIVE, the work request status cannot be changed to WORK ORDER until an approved change request is attached to the work request.

DEFAULT ROUTE FROM ACCOUNT - If this rule key is set to on ON and a work request in Created status is saved with the Approval Route field left blank, the system enters the Work Request route indicated on the referenced Account record. If the DEFAULT APPROVER FROM ASSET rule key is also set to ON this rule key will be overridden.

DEFAULT ROUTE FROM ASSET - If this rule key is set to on ON and a work request in Created status is saved with the Approval Route field left blank, the system enters the Work Request route indicated on the referenced Asset record. If both the DEFAULT APPROVER FROM ACCOUNT rule key and this rule key are set to ON the system uses this rule key.

INCLUDE P WORK TYPE - When the status of this rule key is set to on the system will include P type Work Orders when showing possible duplicate work records as a new work request is created.

Batch Processes

Purge Work Requests - sdbp_purge_work_requests;

Allows you to enable or disable a batch job to purge work requests in Work Order status where the work order is in a certain status. Status and age are defined in the Batch Purge Parameters and Batch Purge Criteria business rules.

Code Tables

Code Table 10: Failure Codes (Length = 10)

Failure Code field - Define types of equipment failure that may occur. Typical Failure

Codes may include Corrosion, Distortion, Erosion, etc.

Code Table 110: Backlog Group (Length = 6)

Backlog Group field - These groups can be used to group crews or to find and categorize work orders at a high level. This code table is used in the Process, Asset, Function, Work Request, Work Order, and Crew Activity Log modules.

Code Table 25: Building Codes (Length = 20)

Building field - Define building identifiers for the asset location specific to your organization. The Building field is searchable from the Search Options screen, and can be useful in finding assets when only the building location is known.

Code Table 2: Maintenance Classes (Length = 10)

Class/Catg. field (first field) - Define classes describing types of work. The Maintenance Class field can be searched on the Work Request and Work Order Search Options screens.

Code Table 3: Maintenance Categories (Length = 10)

Class/Catg. field (second field) - Define categories describing types of work. The Maintenance Category field can be searched on the Work Request and Work Order Search Options screens.

Code Table 40: Criticality Codes (Length = 1)

Criticality field - The criticality number represents the relative work or safety impact of the asset. This number is later used by the system to calculate the overall priority of work orders.

The system contains default entries for Code Table 40, however, you can alter the data. We recommend that only the Description field be altered if necessary since the numeric values (1-9) are used in the calculation of priority on work orders and work requests.

Code Table 41: Work Priority Codes (Length = 1)

Priority field (second field) - Define codes that indicate the relative work or safety impact of the work that is to be done. This information is later used by the system to calculate the overall priority of work orders.

By default the system contains entries for Code Table 41. The user has the ability to alter the data in this Code Table, however we recommend that only the Description field be altered if necessary since the numeric values (1-9) are used in the calculation of Priority.

Code Table 139: Downtime Codes (Length = 10)

Type field (next to Downtime check box) - Define downtime types. Typical Downtime Codes might be 'Shutdown', 'Annual Turnaround', etc.

Copy Record

WORKREQ - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more

information.

Create Work Request

Grants the ability to create a Work Request record. This function adds the Create Work Request action to the home page Actions list.

Create Work Request Asset

Grants the ability to create a Work Request record by selecting the action on an Asset record.

Create Work Request Component

Grants the ability to create a work request by selecting the action on a Component record.

Create Work Request Fleet Asset

Grants access to the Create Work Request action from Fleet Asset records.

Create Work Request Process

Grants the ability to create an Work Request record by selecting the action on a Process record.

Reports

S_RPT042 - Work Request Summary Report

Lists information from a work request.

Work Design Module

Fields

Sequence No.: Work Design No.

The record number is comprised of a unique ID (Ex. “0700014”). Work Design numbers are usually system-generated.

TABLE NAME - SA_WORK_DESIGN - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Approval Route Field

Designate approvers for work designs the Approval Limits module of the Administration subsystem under Approvals and Routes.

Business Rules

Compatible Unit Function Rule

Business Rule COMPATIBLE UNIT FUNCTION

Rule ID: COMPATIBLE UNIT FUNCTION | Business | List | Limit?

Desc: This rule is used to associate whether work done on a compatible unit is categorized as new, retire or existing depending on the function.

Comment: Enter a function and type to categorize a compatible unit with that function as new, retire, or existing for the CU Summary view in Work Design.

Function	Type
CODE 1	Existing
CODE 2	Existing
INSTALL	New
REMOVE	Retire
RETIRE	Retire
ROTATE	Existing
TRANSFER	Existing

Description: Synergen Default Code

This rule is used to associate whether work done on a compatible unit is categorized as new, retire or existing depending on the function. Enter a function and type to categorize a compatible unit with that function as new, retire, or existing for the CU Summary view in Work Design.

PO Report Constants Rule

Business Rule PO REPORT CONSTANTS

Rule ID: PO REPORT CONSTANTS | Business | Parameter | Limit?

Desc: This rule defines the "constants" for Purchase Orders and Requisitions. Constants are defined as fields consistently used on each report and may include bill to address; ship to address and company name.

Comment: Enter into the description fields the text you would like to appear on the Purchase Order and Requisition reports.

Address Field		Max Lines
ADDRESS_FOR_BILL_TO	(use desc)	(use 5 lines)
ADDRESS_FOR_SHIP_TO	(use desc)	(use 5 lines)
AUTO_PAY_TEXT		
LABEL_DUTY_TAX	Duty:	
LABEL_FEDERAL_TAX	GST:	
LABEL_STATE_TAX	PST:	
LOWER_LEFT_BOTTOM_BOX	(use desc)	
LOWER_LEFT_TOP_BOX	(use desc)	
STANDARD_EMAIL_BODY_TEXT	(use desc)	
TAX_BOX	(use desc)	(use 9 lines)
YOUR_COMPANY_NAME	(use desc)	(use 1 line)

Description: Synergen Associates, Inc. 2121 North California Blvd., Suite 800 Accounts Payable Department, Walnut Creek, California 94596

The value entered for the LABEL_DUTY_TAX key is displayed on the Design Estimate view of the Work Design module. If no value is entered here "Duty" is used as the default label.

Address Field and Max Lines

LABEL_DUTY_TAX - The label entered here is displayed on the Design Estimate view of the Work Design module. If no value is entered here “Duty” is used as the default label.

Work Design Phase Rule

The screenshot shows the configuration window for the Business Rule **WORK DESIGN PHASE**. The Rule ID is **WORK DESIGN PHASE**, and it is categorized as **Business**. The description is "This rule defines the phases of work designs." The comment is "Enter a phase and corresponding optional sequence number to determine the order in which the phase appears in the list of values on Work Design screens. The phase with the lowest sequence number will".

Phase	Sequence No.
PHASE 1	5
PHASE 2	10
PHASE 3	15
PHASE 4	2

There is also a Description field at the bottom of the window.

Use this rule to define the phases that are used on work design records for your organization. The corresponding sequence number determines the order in which the phase appears in the list of values on the Work Design screen. The phase with the lowest sequence number will be the default phase when new Work Design records are created.

Work Design Processing Rule

The screenshot shows the configuration window for the Business Rule **WORK DESIGN PROCESSING**. The Rule ID is **WORK DESIGN PROCESSING**, and it is categorized as **Business**. The description is "This rule defines options available for work design processing." The comment field is empty.

Option	Status
APPEND WORK SITE TO WO TASK	ON

There is also a Description field at the bottom of the window.

This rule defines options available for work design processing.

APPEND WORK SITE TO WO TASK - Set this rule key to YES to have the system copy work site information into the description field on task records created from the work design.

Code Tables

Code Table 22: Vendor Characteristic Types (Characteristics View)

Contractor field - Define contractors which can be added on in the Compatible Units Contractor Bids view. The values are carried over when the compatible unit is referenced on work records.

Code Table 23 - Units for length (Length = 4)

Location view - Length field.

Code Table 159: Federal Tax Codes (Buyer Data View) (Length = 1)

Federal field - The code can only be one character long and the Description should contain the percentage rate in the first six characters of the field.

Code Table 160: State Tax Codes (Buyer Data View) (Length = 1)

State field - The code can only be one character and the Description should contain the percentage rate in the first six characters of the field.

Code Table 161: Duty Codes (Buyer Data View) (Length = 1)

Duty field - The code can only be one character long and the Description should contain the percentage rate in the first six characters of the field.

Code Table 730: Contribution in Aid to Construction (Length = 30)

Contribution Type field - Define codes to distinguish the types of contributions that might be made toward construction projects.

Code Table 731: Work Design Cost Type (Length = 30)

Cost Type field - Define codes to distinguish the types of costs that might be made toward construction projects.

Code Table 732: Location Structure Type (Length = 30)

Structure Type field - Define codes to distinguish the types of location structures that might apply for construction projects.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

UPDATE PRICING FOR WD

Grants access to the action which updates the pricing of all material, labor and equipment items on the work design.

CREATE WO FROM WORK DESIGN

Grants access to the action which creates a work order from the details on the Work Design record.

ROUTE TO DESIGNER

This function only applies to custom integration processing. Allows a Work Design to be routed to Autodesk AUD Application for design work to be done.

Reports

S_RPT154 - Work Design

Describes the work, location and compatible units needed to perform a job.

S_RPT156 - Work Design Comparison

Shows a comparison between the estimate cost summary of the work design and alternate designs that are specified in the Alternate Designs view of the work design.

S_RPT155 - Work Design Estimate

Shows a summary of cost estimates related to performing a job.

Copy Record

WODESIGN- COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Work Order Module

Fields

Sequence No.: Work Order No.

The record number is comprised of a unique ID (Ex. "0200070"). Work order numbers must be system generated. Manual creation of these record numbers could result in critical system errors when WOs are created from other records or in batch procedures.

TABLE NAME - SA_WORK_ORDER - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.


Please refer to [Sequence Numbers Module](#) for more information and examples.

Approval Route

Designate Approval Routes for work orders in the Approval Limit module under Approvals and Routes in the Administration subsystem.

Business Rules

Alerts Rule



Alert	Recipient
▲ BACKORDERED ITEMS HAVE ARRIVED	REQUESTOR
PARTS HAVE ARRIVED	REQUESTOR
PO ITEM RECEIVED	REQUESTOR
WORK ORDER HAS BEEN APPROVED	REQUESTOR
▼	

This business rule identifies system alerts that are available and who should receive the alert. New Alert types cannot be created.

Alert and Recipient

BACKORDERED ITEMS HAVE ARRIVED - Work Orders and Checkout Requests - Enter REQUESTOR in the Recipient column to have an alert sent to the requestor when backordered items come in. The requestor who's Issue Ticket Report has been printed will receive the alert.

PARTS HAVE ARRIVED - Work Order - Enter REQUESTOR or PLANNER in the RECIPIENT column to have an alert sent to the requestor or planner of a work order with a direct purchase is received in the Receiving module. The default is REQUESTOR. When this is set to PLANNER the alert is sent to the planner indicated on the work order task, not on the work order.

PO ITEM RECEIVED - Requisition - Enter REQUESTOR in the PO ITEM RECEIVED column to have an alert sent to the requestor identified on the Requisition when the requested PO item is received.

WORK ORDER HAS BEEN APPROVED - Work Order - Enter REQUESTOR in the RECIPIENT column to have an alert sent to the work order requestor when approval has been processed for the work order.

WO FINISH WITH OPEN PO OR REQ - Purchase Order, Requisition - Enter the person who should receive an alert when a Work Order that references an open purchase order or requisition is set to Finished status. The Default setting is to BOTH.

Batch Purge Criteria Rule

Business Rule BATCH PURGE CRITERIA

Rule ID: BATCH PURGE CRITERIA Business Parameter Limit?

Desc: This rule defines criteria for batch purge processing.

Comment: Batch processing. Define rule keys to specify criteria for purging of data in batch jobs.

Batch Processing	Status 1	Status 2	Status 3	Status 4
EVENT QUEUE STATUSES	FAILED	FAILED		
REQUISITION PO STATUSES	CLOSED	CANCELED		
WORK REQUEST WO STATUSES	CLOSED	CANCELED	REJECTED	HISTORY

Description: Work requests associated to work orders in the statuses entered in the Status 1 - 4 columns are purged. For example, if the value in the Status 1 column is set to CLOSED, the system purges any work requests associated to

Define the status values which determine when to delete obsolete data. Records are deleted when batch purge processing runs. Enter the applicable statuses in the Status 1, Status 2, and Status 3 columns for each record type. For example, for work requests, if the value in the Status 1 column is set to CLOSED, the system purges any work requests associated to work orders in CLOSED status.

Batch Processing

EVENT QUEUE STATUSES - Delete event queue entries that are in the statuses identified in the status columns.

REQUISITION PO STATUSES - Delete requisitions associated with purchase orders in the statuses identified in the status columns. Typically, Requisitions are considered unnecessary after the PO has been CLOSED or CANCELED.

WORK REQUEST WO STATUSES - Delete work requests associated to work orders that are in the statuses identified in the status columns. Recommended options for Status 1 - 4 include work orders in CLOSED, CANCELED, HISTORY, or REJECTED status. Although it is possible, it is NOT recommended that you purge work requests associated to work orders in PLANNING, PENDING APPROVAL, APPROVED, ACTIVE or FINISHED status.

STATUS 1, STATUS 2, STATUS 3 - These columns indicate the statuses for the records that are purged. Status 1 is the prime status to be deleted. Status 2 and 3 are other desired statuses.

Batch Purge Parameters Rule

Batch Parameters	Days
ALERTS	1
AUDIT LOG	0
BATCH_MESSAGES	7
EVENT QUEUE	5
REQUISITIONS	9
WORK REQUESTS	0

Description
Alerts are those records generated by the system when a defined event occurs requiring user attention. Alerts may be accessed (per user) via the WorkFlow Agent. Purge processing compares the Alert Date to the current

As system data ages, it often becomes of little or no value to users. Purging old data regularly prevents tables from growing too large and helps maintain a quick system response time when querying those tables.

The Batch Purge Parameters Rule defines, per specific type of data, the age of a record before batch processes purges it. Note that the specific routines called for purging are already defined, purging either a single record at a time or a header record and its associated view, whichever is appropriate.

Batch Parameters and Days

ALERTS - Set the number of days the system should retain Alerts on the home page. Purge processing compares the Alert Date to the current date minus the number of days listed in the DAYS column, and deletes any messages that fall outside of that range.

AUDIT LOG - Set the number of days the system should retain Audit Log entries. Purge processing compares the date that the entry was made to the current date minus the number of days listed in the DAYS column, and deletes any messages that fall outside of that range.

BATCH_MESSAGES - Messages generated by batch processing and are stored as records in the Job Manager module so that you can easily access and review them at any time. Purge processing compares the Batch Message Date to the current date minus the number of days listed in the DAYS column, and deletes any messages that fall outside of that range.

REQUISITIONS - Purge Processing compares the PO Status Date (for status settings in the Batch Purge Criteria business rule) to the current date. When the result is greater than the number of days listed in the DAYS column, the Requisition is deleted from the system.

WORK REQUESTS - Purge Processing compares the Work Order Status Date (for status settings in the Batch Purge Criteria business rule) to the current date. When the result is greater than the number of days listed in the DAYS column, the work request is deleted from the system.

Planner Rule

Code	Full Name	Username
123456	Max Length	BYB_USER_1
BYB1	Branwen Y. Burgess	BRANWEN
RLW	Ray Winther	RAY
RVM	Raya Veksler	RVEKSLER
SRP	sudha's	SREDDY
WWW	Nolan and Lauren's D	WILLY

Define planner codes, and identify the full names and usernames associated to each code. These codes are used when identifying a planner on work records.

The user associated with the code receives an alert when an event occurs where an alert would be sent to the planner. For example, when a planner plans parts against a work order and needs to be notified when the parts have arrived. This does not mean that the system is configured to send alerts regarding any record where a planner is indicated.

Code

Enter the codes for planners in the Code column. Each code must be unique.

Full Name

Enter the full name of the person associated with the code. A person can be listed on more than one code.

Username

Enter the username of the person associated with the code. Since a person can be listed on more than one code, the username can be listed more than once as well.

S_RPT071 Crew Craft Columns Rule

Business Rule S_RPT071 CREW CRAFT COLUMNS

Rule ID: S_RPT071 CREW CRAFT COLUMNS Configuration: List Limit?

Desc: This rule is used to designate the three main crafts for each crew for Report 71. Report 71 (the Work Order Forecast Report) will retrieve the estimated hours for the three main crafts. For Report 71 to work,

Comment:

Crew	Craft #1	Craft #2	Craft #3
BYB	TECH	MECH	ELEC
DP1	TECH	CARP	MECH
GE	ELEC	MECH	PLMR
MASON	CARP	CUST	ELEC

Description:

Designate the three main crafts for each crew entered on Report 71 - Work Order Forecast Report. The system will retrieve the estimated hours for the three main crafts. For Report 71 to display the correct information, the crew and craft must be listed in this rule.

Crew, Craft #1, Craft #2, Craft #3

For each crew entered in the Crew column, a craft needs to be entered in Craft #1. If a crew has more than one craft, use Craft #2 and Craft #3 columns. Several crews can use a single craft.

Work Order Aging Rule

Business Rule WO AGING

Rule ID: WO AGING Configuration: Parameter Limit?

Desc: This rule defines the number of days a Work Order remains in CLOSED status before batch processing archives the Work Order (and all associated details) to the History Work Order module.

Comment: Batch processing.

Data Aging	Days
AUTO_CLOSE_AFTER	0
RETAIN_DAYS	0

Description: Indicates the number of days after which work order status will be changed to CLOSED.

Define the number of days a work order remains in CLOSED status before batch processing archives the work order (and all associated details) to the History Work Order module.

Data Aging, and Days

AUTO_CLOSE_AFTER - The system will automatically change the work order status from FINISHED to CLOSED this number of day after the status is set to FINISHED.

RETAIN_DAYS - The number of days the work order will remain in CLOSED status before batch processing archives the work order to History.

Work Order Processing Rule

Please see the description of the [Work Order Processing Rule](#) from Work Order Task chapter.

Work Priority Defaults Rule

Initial Work Order Type	Work Priority
EMERGENCY	9
REGULAR	1
URGENT	5

Establish default Work Priorities for Initial Work Order Types on Work Request records.

Initial Work Order Type

EMERGENCY - The highest priority work orders can be set as EMERGENCY work orders. Authorized users can select Create Emergency Work Order from the Actions list on the home page to create Emergency Work Orders very quickly.

REGULAR - The lowest priority work orders for routine work.

URGENT - Mid-level priority work.

Work Priority

The lower numbers indicate a low priority, and higher numbers indicate high priority.

Batch Processes

Close Work Order - sdbp_close_work_orders;

Closes work orders in Finished status after the number of days specified in the WO Aging Business Rule.

Held for Parts - sdbp_held_for_parts;

Reviews Work Order Task Parts Requirements vs. stock inventory and direct purchases for a task. If the On-Hand quantity in a storeroom is less than the amount required for an active task or if direct purchase items ordered for a task are still not received, the Held for Parts indicator on the task is checked. If all parts required (storeroom and direct purchase) are available, the Held for Parts indicator is unchecked.

PM Cycle - sdbp_pm_cycle_job.start_job;

Reviews active PM Masters and cycles those that are due, creating work orders in the status defined in the PM Master Parameters Business Rule. If the PM is being cycled and the benchmark's component is no longer installed on the benchmark's asset, the system generates a work order with the asset from the benchmark and will not bring over the component.

Process Service Timesheet - sdbp_process_service_timesheet.post_approved_time;

Processes approved labor costs (from service timesheets) that have not yet been posted. Costs are posted to the work order task as a Labor record. If a Labor Requirement record does not yet already exist for the task, the system inserts one, then posts the cost. Once a labor charge is successfully processed, it is marked as posted.

Purge Work Order - sdbp_purge_work_order.purge_wo;

Selects the work orders that have been in Closed status for the number of days as defined in the Work Order Aging Rule, then copies them into the Work Order History tables. Each selected work order is reviewed to see how much information is to be moved to the History tables (defined in the Work Order Closeout detail). Asset History information is also inserted. Once a work order is successfully processed, the work order is deleted from the work order tables.

Purge Work Requests - sdbp_purge_work_requests;

Allows you to explicitly enable or disable a batch job to purge work requests in WORK ORDER status where the work order is in a certain status. Status and age are defined in the Batch Purge Parameters and Batch Purge Criteria business rules.

Finish WO - sdbp_finish_wo;

Updates the work order header status to Finished if either all associated tasks are in Closed, Canceled, or Finished status, or if the work order has no associated tasks.

PM Finish - sdbp_pm_finish;

Processes PM Master information for those PMs where the associated work order has been set to Finished status. This includes entering the work completion date, inserting a new Forecast record (to maintain the correct number of future cycles), and setting any skipped forecast dates to Canceled status. The next schedule date is recalculated (for calendar interval PMs) and is placed on the PM Master record.

Reset Demand Quantity - sdbp_storeroom_demand;

Recalculates the on-demand quantity for parts within the storeroom. This procedure reviews all active work order tasks, summing the quantities required across tasks for stock items. Once recalculated, the on-demand quantity for each storeroom item is updated accordingly. Note that this batch procedure is not a required procedure since standard processing maintains the storeroom on-demand quantity. This serves as an extra level of assurance that the on-demand quantities are correct as of each nightly batch run. Note that running this process could potentially be time consuming if there is a large amount of data for the system to process.

Code Tables

Code Table 2: Maintenance Classes (Length = 10)

Class/Catg. field (first field) - Define classes describing types of work. The Maintenance Class field can be searched on the Work Request and Work Order Search Options screens.

Code Table 3: Maintenance Categories (Length = 10)

Class/Catg. field (second field) - Define categories describing types of work. The Maintenance Category field can be searched on the Work Request and Work Order Search Options screens.

Code Table 41: Work Priority (Length = 1)

Priority field (second field) - Define codes that indicate the relative work or safety impact of the work that is to be done. This information is later used by the system to calculate the overall priority of work orders.

By default the system contains entries for Code Table 41. The user has the ability to alter the data in this Code Table, however we recommend that only the Description field be altered if necessary since the numeric values (1-9) are used in the calculation of Priority.

Code Table 110: Backlog Group (Length = 6)

Backlog Group field - These groups can be used to group crews or to find and categorize work orders at a high level. This code table is used in the Process, Asset, Function, Work Request, Work Order, and Crew Activity Log modules.

Code Table 120: Crew Event Types (Length = 15)

Event Type field - Define codes to identify stages completed by a crew in the work process. Examples include Finish (indicates finished work on a work order task), Start (identifies a started task), etc. This code table is also used in the Crew Activity Log module.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Activate WO Material

Grants access to the Activate WO Material Action so that users can activate work order materials prior to setting the entire work order's status to Active.

Add Customer Contributed

Allows user to add a Construction Asset in Planned status from an outside source into the Work Order Task's Construction Assets view.

Allow WO Project Update

Allows users to update the Project / Subproject on Active Work Orders as long as there are no "Actual" costs for that Work Order.

Create Emergency Work Order

Grants the ability to create an Emergency Work Order record from the home page.

Create Emergency WO Fleet Asset

Grants the ability to create an Emergency Work Order record by selecting the action on a Fleet Asset record.

Create Emergency WO Asset

Grants the ability to create an Emergency Work Order record by selecting the action on an Asset record.

Create Permit From WO

Grants access to the Create Permit action available in the on Work Order and Work Order Task records. This action creates a permit for the work record.

Create WO From Benchmark

Grants the ability to create a follow-up Work Order from a Benchmark Work Order record.

Create Work Order

Grants the ability to create a work order. This function adds the Create Work Order action to the home page Actions list.

Create Work Order Process

Grants the ability to create a Work Order record by selecting the action on a Process record.

Create Work Order Fleet Asset

Grants the ability to create a Work Order record by selecting the action on a Fleet Asset record.

Create Work Order Component

Grants the ability to create a Work Order record by selecting the action on a Component

record.

Create Work Order Asset

Grants the ability to create a Work Order record by selecting the action on an Asset record.

Reconcile CU

Grants the ability to adjust actual quantities of contractor supplied compatible units from the CU Worksheet. The Work Order Task record must be in Finished status for this action to be available.

Repair Removed Part

Grants the ability to use the Repair Removed Part action from the Work Order Task module Actions list to create a Material Disposition record.

Search Duplicate Permits

Grants access to the action which allows users to search for duplicate permits for Work Order records. This action is available wherever the "Create Permit" action is available.

Show CU Location

Allows users to access the CU Location and Location Worksheet views on Work Order Tasks. Users must also have the SHOW CU ON WO responsibility.

Show CU on WO

Grants the ability to use Compatible Units functionality on the Work Order Task by selecting CU Worksheet, Contractor Contributed and Item Worksheet from the Views list.

Update Benchmark Work Order

Grants access to the action which allows the user to update a Benchmark Work Order with information from a Work Order that was generated from a PM Master.

Update Process on Work Order

Users with this responsibility are able to change the Process ID on work orders.

Update WO from Benchmark

Grants access to the action which allows the user to update a work order with information from a benchmark work order record.

WO Active to Planning

Grants the ability to change the status of a Work Order from ACTIVE to PLANNING.

WO Closed to Finished

Grants the ability to change the status of a work order from CLOSED to FINISHED.

WO Finished to Active

Grants the ability to change the status of a work order from FINISHED to ACTIVE.

WO Finished to Closed

Grants the ability to change the status of a work order from FINISHED to CLOSED.

WO to Active

Grants the ability to change the status of a work order to ACTIVE.

Work Type Update

Allows users to update the Work Order type for Work Orders types "R", "E" and "U". Updates are not allowed for "P" and "S" types.

Charts

S_CHT123 - Actual Cost to Planning Estimate

Shows percent accuracy of closed work orders' actual and revised estimate against actual costs. The time basis and time units defined in the Charts and Metrics Settings Business Rule under the WO Actual Cost to Planning Est. rule key.

S_CHT124 - Corrective vs. Preventive Work Orders

A comparison of Corrective Work Orders to Preventive Work Orders for the current year and the previous year. The data can be filtered further by Plant, Department and Area. Other filtering options, including Department, Area and Asset, are available in the Chart Field List.

S_CHT145 - Emergency Work Orders

The number of Emergency Work Orders created during the current and previous year. Emergency Work Orders have a type "E". The data can be filtered further by Plant. Other filtering options, including Department, Area and Asset, are available in the Chart Field List.

S_CHT122 - Planning Accuracy

Shows closed work orders that have actual costs compared to original and revised estimates that fall within a set variance. The variance, time basis, and time units defined in the Charts and Metrics Settings Business Rule under the WO Planning Accuracy Index rule key.

S_CHT146 - Preventive Maintenance Investment

The actual amount spent on Preventive Maintenance compared to the total amount spent on maintenance for the current and previous year. The data can be filtered further by Plant. Other filtering options, including Department, Area and Asset, are available in the Chart Field List.

S_CHT151 - Work Order Aging

The number of days Active Work Orders have been open. The number of days is grouped into Intervals such as "0 to 2 Days", "3 to 6 Days", etc. The data can be filtered further by Plant, Work Type, Crew, and Criticality. Other filtering options, such as Department and Area, are available in the Chart Field List.

Metrics

S_MTRC5 - Percent Preventive Work - sdbp_metric_pct_pm_wos

This metric is to describe the relationship between the number of PM Work Orders and the total number of Work Orders as a percentage. A PM Work Order is a Work Order with work type "P". It provides a means to monitor and improve the ratio of the number of PM Work Orders versus the total number of Work Orders.

S_MTRC10 - Percent PM Investment - sdbp_metric_pct_pm_investment

This metric is to describe the relationship between the PM Work Order dollars and the total dollars of all Work Orders as a percentage. A PM Work Order is a Work Order with work type "P". It provides a means to monitor the dollar amount being invested in preventive maintenance versus the total dollar amount used for maintenance.

S_MTRC7 - Percent Emergency Work - sdbp_metric_pct_emergency_wos

This metric is to describe the relationship between the number of Emergency Work Orders and the total number of Work Order as a percentage. An emergency Work Order is a Work Order with work type "E". It provides a means to monitor and improve the ratio of the number of Emergency Work Orders versus the total number of Work Orders

Reports

S_RPT046 - Work Order Aging Report

Lists active work orders and the number of days the work order has been backlogged. The date that the work order was activated is subtracted from the current date to determine the number of backlog days.

S_RPT091 - Historic Cost Performance by Asset Report

Lists assets and work orders and their associated Labor and Material costs.

S_RPT078 - Holiday Overtime Standing Report

Provides a listing of Employees for holiday call-in overtime.

S_RPT026 - Inventory Picklist Report

Lists stock items to be issued from the storeroom. This report can be used to provide storeroom personnel a means to prepare stock for pickup or delivery. It can be built by either planning stock items on a work order before the work order is activated or by creating a checkout request.

Note: S_RPT026B is the bar code font version of this report.

S_RPT048 - Work Order (Condensed) Report

This report is a condensed Work Order report, returning all tasks for the Work Order.

S_RPT071 - Work Order Forecast Report

Lists scheduled work orders and craft hours needed by crew. The values shown in the Craft fields (Tech, Carp, Mech) are defined in the S_RPT071 Crew Crafts Columns Business Rule.

S_RPT044 - Work Order Package Report

A complete work order package that can be given to the person performing the work. Space is available for written comments to be entered later as closeout information.

Work Order Task Module

Business Rules

Credit Card Purchases Rule

Business Rule CREDIT CARD PURCHASES

Rule ID: CREDIT_CARD_PURCHASES Business Parameter Limit?

Desc: This rule controls whether or not direct purchase items may be paid for using a credit card.

Comment: To control which document types (such as Purchase Orders) may be charged against a credit card, list the document types in the "DOCUMENT TYPE" column and set the "OPTION STATUS" column to ALLOW or

Document Type	Option Status
PURCHASE ORDER	DISALLOW
REQUISITION	DISALLOW
WORK ORDER	ALLOW

Description: Allows user to charge direct purchases against a credit card.

Control which types of documents are valid for direct purchase items to be paid for using a credit card. Direct Purchase items can be paid for using a credit card number (associated with an Employee record) as the charge number.

Document Type and Option Status

PURCHASE ORDER, REQUISITION, WORK ORDER - Allows or prevents users from charging direct purchases against a credit card. Enter ALLOW to enable charging of direct purchases to credit card numbers or DISALLOW to prevent it for each document type.

Criticality Override Rule

Business Rule CRITICALITY OVERRIDE

Rule ID: CRITICALITY_OVERRIDE Business Parameter Limit?

Desc: This rule allows the criticality field (selected from the Asset module) to be modified when copied to a Work Order or a Work Request. Such processing is appropriate when Asset records do not have the correct

Comment: Default processing is DISALLOW.

Module	Option Status
WORK ORDER	ALLOW
WORK REQUEST	ALLOW

Description: The criticality field is not available for update in the Work Order and Work Order Task modules.

Control modification of the Criticality field on Work Orders and Work Request records. The Criticality field is copied onto work records when an asset is referenced. Set the option status to Allow or Disallow to control whether or not the field can be modified. Allowing modification is appropriate if your asset records generally have no criticality or

an incorrect criticality assigned to them.

The Criticality field is the first Priority field on work records. Default processing for this rule is DISALLOW.

Default Backlog Groups Rule

Business Rule DEFAULT BACKLOG GROUPS

Rule ID: Business List Limit?

Desc: This rule allows a user to build a relationship between a crew and a backlog group.

Comment: The following modules are affected by this Business Rule:
Work Request, Work Order, Work Order Task, Benchmark Work Order and PM Master (detail - Additional)

Crew	Backlog Group
BYB	BYBBLG
CAK1	CAKBGLG
DP1	DEPOT1
GE	CAKBGLG
LAB	BYBBLG
MASON	DEPOT1
RJB	RJBBLG
RVM	RVMBLG

Description:

Build a relationship between crews and backlog groups for Work Requests, Work Order Tasks, Benchmark Work Order Tasks, PM Masters, and on schedules.

An example of how the concept of a backlog crew may be used is that Crew A (Crew) works 1st shift and Crew B (Backlog Group) works 2nd or 3rd shift and takes on any unfinished tasks originally scheduled for Crew A (Crew) on 1st shift.

Crew and Backlog Group

Enter the crews and the associated backlog groups for each in the appropriate columns.

Planner Rule

Business Rule PLANNER

Rule ID: Business List Limit?

Desc: This rule allows you to define the codes for Planners and to identify the full name of the Planner. For alerts that are sent to Planners, this rule also allows you to identify the Username.

Comment: Note: This Rule replaces Code Table 135.

Code	Full Name	Username
123456	Max Length	BYB_USER_1
BYB1	Branwen Y. Burgess	BRANWEN
RLW	Ray Winther	RAY
RVM	Raya Vekslar	RVEKSLER
SRP	sudha's	SREDDY
WWW	Nolan and Lauren's D	WILLY

Description:

Define planner codes, and identify the full names and usernames associated to each code. These codes are used when identifying a planner on work records.

The user associated with the code receives an alert when an event occurs where an alert would be sent to the planner. For example, when a planner plans parts against a work order and needs to be notified when the parts have arrived. This does not mean that the system is configured to send alerts regarding any record where a planner is indicated.

Code

Enter the codes for planners in the Code column. Each code must be unique.

Full Name

Enter the full name of the person associated with the code. A person can be listed on more than one code.

Username

Enter the username of the person associated with the code. Since a person can be listed on more than one code, the username can be listed more than once as well.

PM Route Options Rule

Name	Option	Value
ALLOCATE COSTS TO ASSETS	ON	APPROVED

Control parameters used in PM Route processing.

Name, Option, and Value

ALLOCATE COSTS TO ASSETS - If you set the Allocate Costs to Assets rule key to ON, the system will manage the costs for a work order task on a PM Route so that the costs are evenly distributed among the assets on the route. The system completes this re-distribution of costs by creating cost adjustment records.

The value is the status that the adjustment records will be created in.

Validate Task Report Codes Rule

Business Rule VALIDATE TASK REPORT CODES

Rule ID: Business Limit?

Desc: This rule is used to validate report codes on a Work Order Task.

Comment:

Validation	Option Status
REPORT_CODE	ON
REPORT_CODE1	OFF
REPORT_CODE2	OFF
REPORT_CODE3	ON
REPORT_CODE4	OFF
REPORT_CODE5	OFF

Description: The default is set to OFF. This will be used for all reporting codes if they are not defined here.

Establish which report codes should be validated work order tasks.

Validation and Option Status

Work order task records include five report code fields. If the Option Status is set to OFF in this Business Rule these fields are essentially free form. If the Option Status is set to ON the system limits entry of Report Codes to the codes available on the Lists of Values. These lists are controlled by Code Tables 281-285.

Any report codes that are not defined here are defaulted to OFF.

Variable Expense Codes Rule

Business Rule VARIABLE EXPENSE CODES

Rule ID: Configuration Limit?

Desc: This rule is used to allow the ability to change expense codes during stock checkout and planning of Work Order Materials until the expense codes are actual.

Comment:

Rule	Option
DISPLAY EXPENSE CODES	YES
FORCE UNIQUE EXPENSE CODES	NO
OVERRIDE EXPENSE CODES	NO

Description:

This rule determines how expense codes are handled during stock checkout, checkout request, planning work order task materials and labor, and in the Timekeeping module. Regardless of the settings in this rule, any desired changes to expense codes can only be made before costs are actualized. Once actual costs are applied, the expense code on the record cannot be changed.

Rule and Option

DISPLAY EXPENSE CODES - If you enter YES as the option, the system will display the Regular and Premium Expense Code fields on the employee Timesheet, and the Expense

Code field on the Issue Ticket for stock checkouts based on Work Orders. Enter NO and the field is not displayed.

FORCE UNIQUE EXPENSE CODES - If you enter YES for this option, work order time charges for the same craft must have the same expense codes. The default setting is YES.

OVERRIDE EXPENSE CODES - Enter YES or NO in the OPTION column to allow or disallow users to change expense codes on timesheets, issue tickets for stock checkout, stock checkout requests, and material and labor detail records on work order tasks.

Entering YES in the OPTION column has the following implications:

- Materials planners will be able to overwrite the default expense codes for the Materials view of the Work Order module in the Maintenance subsystem. The system defaults this information from expense code associated with the Stock Code and Storeroom.
- Employees responsible for creating Issue tickets for stock item checkouts will be able to change the associated Expense code.
- The system will display the Regular and Premium Expense Code fields on the employee Timesheet, and the Expense Code field on the Issue Ticket for sock checkouts based on Work Orders. This includes expense codes that have been provided by planners.
- Labor planners will be able to overwrite the default expense codes for Regular and Premium labor on Work Order Tasks. The system defaults this information from the Craft associated with the Work Order Task.
- Workers who enter their own time into the Timekeeping module of the Maintenance subsystem, will be able to change the Regular and Premium labor information brought over from the Work Order Task on timesheet entries based on Work Orders. This includes expense codes that have been provided by planners.
- Supervisors who review timesheets will be able to change the Regular and Premium labor information brought over from the Work Order Task on timesheet entries based on Work Orders. This includes expense codes that have been provided by planners and/or changed by employees on their timesheets.

Combining the Rules:

To keep anyone from changing expense codes:

Display Expense Codes = NO

Force Unique Expense Codes = YES

Override Expense Codes = NO

To allow only Planners to use variable expense codes:

Display Expense Codes = NO

Force Unique Expense Codes = YES

Override Expense Codes = YES

To allow charges for the same craft to use different expense codes:

Display Expense Codes = YES

Force Unique Expense Codes = NO

Override Expense Codes = YES

Work Order Processing Rule

Business Rule WORK ORDER PROCESSING

Rule ID: WORK ORDER PROCESSING Business Parameter Limit?

Desc: This rule controls specific Work Order processes as specified in the "WO Processing Rule" column.

Comment: DIRECT PURCHASE determines a Requisition is to be created for direct purchase items estimated on a Work Order Task. When the Task is activated, listed direct purchase items are processed, creating a Requisition. You can determine the status of the Requisition by setting the Requisition status in the Value column.

WO Processing Rule	Document	Status	Value
ALLOCATE COSTS TO ASSETS		OFF	APPROVED
APPLY CHANGE REQ CREATED FR WO		ON	
AUTO ADD DEPENDENT MATERIALS		ON	
AUTO CLOSE CHECKOUT REQUESTS		ON	
AUTO UPDATE TRAVEL TRIPS		ON	
BUYER CODE	REQUISITION		GST
CHANGE REQUEST ENFORCEMENT		ON	
CHECK OPEN MATERIAL RECORDS		ON	
COPY EMERGENCY WO TO SCHEDULE	DAILY	ON	NEXT
DELAY CONSTRUCTION ASSET VALUE		ON	
DIRECT PURCHASE	REQUISITION	PENDING APPROVAL	
DIRECT PURCHASE BLANKET		ON	
DIRECT PURCHASE DUTY TAX			0

Description: Set this rule key to ON to have the system reverse asset costs on work order tasks and distribute the costs across assets on the asset list by creating adjustment records. The status of the resulting Cost Adjustment record will be the status entered in the Value column. Choose CREATED if your business process requires that the records be reviewed before they are approved and processed. Choose APPROVED status if the cost adjustments can be created and approved without review. If this rule key is set to OFF, costs are not allocated across the assets.

Control work order processes.

WO Processing Rule, Document, Status and Value

ALLOCATE COSTS TO ASSET - Set this rule key to ON to have the system reverse asset costs on work order tasks and distribute the costs across assets on the asset list by creating adjustment records. The status of the resulting Cost Adjustment record will be the status entered in the Value column. Choose CREATED if your business process requires that the records be reviewed before they are approved and processed. Choose APPROVED status if the cost adjustments can be created and approved without review. If this rule key is set to OFF, costs are not allocated across the assets.

ALLOW NULL ASSET ID - Indicates whether or not a work order that includes construction assets can be set to Closed status without entering an Asset ID in the Work Order Task Construction Asset view. The default setting is OFF.

This applies to Construction Asset records on Work Order Task records with the Action of RETIRE or INSTALL.

With this rule key set to ON, an Asset ID is not required for construction assets with the Retire or Install action, and the asset valuation process occurs the first time SDBP_WORK_ORDER.FIXED_ASSET is run after the work order is set to Closed status. Please note that with this setting, Change Requests cannot be created for the construction assets, so the APPLY CHANGE REQ CREATED FR WO rule key should be set to OFF.

If the rule key is set to OFF, an Asset ID must be entered for construction assets with the Retire or Install action before the work order can be closed. With this setting, asset valuation processing is controlled by the DELAY CONSTRUCTION ASSET VALUE rule key.

It is also important to review your settings in the WO Aging business rule when using this functionality, regardless of whether this key is set to ON or OFF. Make sure that work orders are not sent to history before the valuation takes place. As an extreme example,

you cannot have WO Aging set to 30 days with the fixed asset valuation set to run every 90 days. Once the work order is in history, the valuation will not take place.

APPLY CHANGE REQ CREATED FR WO - This rule key determines whether change requests for construction assets will be applied automatically when created from work orders. If the rule key status is set to ON, the system creates Change Request records based on entries made to the Construction Asset view on the Task and sets those Change Requests to 'Complete' status. The requested changes are automatically posted to the assets. If the rule key status is set to OFF the Change Requests are created and set to 'Created' status so that they must be reviewed before any change is made to the assets. Whether the rule key setting is YES or NO, the 'sdbp_create_change_req.create_change_from_wo' batch process is triggered once the Task status is set to 'Finished' and the Work Order status is set to 'Closed'.

ADD ACTIVE TASK TO WORK ORDER - If this option is set to ON, new tasks are added to Active Work Orders in Active status. If this option is set to OFF, all new Tasks are inserted in Planning status and the Work Order header status is automatically reset to Planning status when the first new Task is added.

The Work Order Processing Rule controls the processes specified in the Work Order Processing Rule column.

AUTO ADD DEPENDENT MATERIALS - When the Status setting is OFF (default), Compatible Unit Dependent Material is not automatically added to the Task Items Worksheet. When the setting is ON, the Dependent Material on Compatible Units is automatically added to the Items Worksheet.

AUTO CLOSE CHECKOUT REQUESTS - When this rule key is ON and a Work Order Task is set to Finished status, all Checkout Requests for the Work Order/Task in Created and Active status are set to Closed status. This releases any demand that was placed on the Storeroom in association to the request.

AUTO-POPULATE INSTLD COMPONENT - When this key is ON and the user enters an Asset ID on the work order, the system generates a list of values of installed components for the Component ID field. If there is only a single installed component for that asset, that component ID is automatically populated. If this key is OFF, the system does not generate the list of values and the user must manually enter the Component ID.

AUTO UPDATE TRAVEL TRIPS - When this key is ON, the Number of Trips for Travel Time is automatically updated based on labor requirement durations whenever a task, labor requirement or an 'L' type task item worksheet record is inserted or updated.

BUYER CODE - This determines if a buyer code is to be added to the direct purchase requisition if there is no buyer code in the material record. Select from the list of values in the Value column the buyer code to use. The document name REQUISITION must be entered in the Document column.

CHANGE REQUEST ENFORCEMENT - If the value in the Status field is set to ON, the Work Order record status cannot be changed to ACTIVE unless an approved Change Request is attached to the task(s) that have change requests required. The Document and Value fields are left blank for this rule key.

CHECK OPEN MATERIAL RECORDS - If the value in the Status field is set to ON, the system looks for unresolved material records when a Work Order Task record is set to Finished Status. If there are unresolved material items, the system displays a warning message. Users can then click the "Details" button to view a list of the unresolved documents. From the list, users can drill-down on the Document ID to open the record (all except Material type since it is on the task material). The Default value for this rule key is OFF. The Document and Value fields are left blank for this rule key.

Unresolved material records could be open requisitions, purchase orders, request for quotes, material dispositions, checkout requests, or storeroom demand set from task materials.

COPY EMERGENCY WO TO SCHEDULE - This rule key determines whether or not emergency work orders are copied to a schedule when they are created. It also determines whether the work order is copied to a daily or workweek schedule.

If the Status field is set to ON, emergency work orders will be copied to a schedule. Set the Document field to either Daily or Workweek to indicate the type of schedule to copy to. Set the Value field to one of the following four options:

Current - Emergency work orders are copied to the current schedule.

Next - Emergency work orders are copied to the next available schedule.

Auto - Emergency work orders are copied to a schedule determined by the crew hours / workweek. If the current time falls within the current schedule (daily or workweek as appropriate) the work order will copy to the current schedule. If the current time falls outside of the current schedule, the work order will copy to the next available schedule.

Manual - User enters the schedule date the work order copies to.

DELAY CONSTRUCTION ASSET VALUE - If this rule key is set to ON, construction assets are not valued until after SDBP_YEAR_END_OH_COST_DIST (indirect overhead) is run based on the schedule established in the Regulatory Account Options Business rule. If it is set to OFF, construction assets are valued the first time SDBP_WORK_ORDER.FIXED_ASSET is run after the work order is set to Closed status. This rule key is only functional if the ALLOW NULL ASSET ID rule key is set to OFF.

DIRECT PURCHASE - This rule key sets the type of purchasing record that should be created for Direct Purchase items on a work order task. When the task is activated the system will create a Requisition for the Direct Purchase items. Determine the status that the Requisition is created in by entering Approved or Created in the Status field. The PO CREATED status can only be used with interfaces. The Value field is left blank for this rule key.

DIRECT PURCHASE BLANKET - If the value in the Status field is set to ON, the system performs the following processing:

When a user planning materials for a Work Order Task (Work Order Task Material and Service Requirement detail) selects a Direct-type stock item and saves the Task record, the system will check for Blanket Contracts that include the item. If it finds one or more contracts, the system requires completion of the Blanket Contract field. If the item is listed on only one active contract, the system will supply the contract's number. If more than one contract might apply, the system opens the list of values so that the user can select the appropriate contract.

When the Work Order status is set to Active, the system first checks Allow Automatic Work Order Release? check box the Blanket Contract record. If the check box is not checked, the system will create a Requisition.

If the Allow Automatic Work Order Release? check box is marked, the system will check the Blanket Contract Limit. If the purchases will exceed the contract limit, the system creates a Purchase Order in Created status.

If the Blanket Contract Limit Amount will not be exceeded, the system next checks the User Limit on the Access List view to the Blanket Contract (in the Purchasing subsystem). If this will be exceeded, the system creates a Purchase Order in Created status. If the limit

will not be exceeded, the system creates the Purchase Order in Issued status.

DIRECT PURCHASE FEDERAL TAX - The number entered in the Value field is used as the default Federal Tax Code on work orders. The Document and Status fields are left blank for this rule key.

DIRECT PURCHASE STATE TAX - The number entered in the Value field is used as the default State Tax Code on work orders. The Document and Status fields are left blank for this rule key.

DIRECT PURCHASE DUTY TAX - The number entered in the Value field is used as the default Duty Tax Code on work orders. The Document and Status fields are left blank for this rule key.

EXPENSE CODE UPDATE - This determines if users can update expense codes on the Work Order Task Material screen for direct items with or without stock codes. Enter ALLOW or DISALLOW in the Document field. The Status and Value fields are left blank for this rule key.

LABOR MARKUP ON COST SUMMARY - This key determines if labor markup transactions are included in the Cost Summary views in the Work Order and Project / Subproject modules. Set the value to ON to include the M1, M2 and M3 Labor Markup Transaction Codes in the Cost Summary views. Set the value to OFF if you do not want to include the labor markup values. The default setting is OFF.

PERMIT TEXT - If the value in the Status field is set to ON, then red text will appear on the Work Order or Task record when there are associated permits. The Document and Value fields are left blank for this rule key.

REAPPROVE WORK ORDER - If this rule key value is set to ON and a new work order task is added to an Approved or Active Work Order record, the system changes the status back to Planning and the newly added task is placed in Planning status as well. The work order must be routed to have the new task approved. This also applies for new tasks which are added from a work design. This allows new tasks (including tasks added via a work design) to be added when the work order is in Pending Approval, Approved or Active status.

USE ESTIMATE AS MATERIAL REQUIRED DATE - When this key value is set to OFF the Material Required Date is not auto-populated. When the setting is ON, the Material Required Date for Stock-coded items is defaulted to the Estimated Delivery Date when the Material Record is created and then is updated when the Material Record is activated.

UPDATE CLOSED WORK ORDERS - When this rule key is set to ON, users can update information on closed work records in any views other than the Approvals view, the Task's Regulatory Accounting (Including Costs section), or any of the CU views. If the rule key is set to OFF no fields or views are updatable on the record.

UPDATE FROM BENCHMARK - When this rule key is set to OFF the Created By and Created Date fields are retained from the original Benchmark if a work order or task is created from a Benchmark. If the value is set to ON the system uses the system date and username of the person logged on to populate these fields.

Work Order Task Planning Rule

Business Rule WORK ORDER TASK PLANNING

Rule ID: Business Parameter Limit?

Desc: This rule defines the planning phases of work order tasks.

Comment: Enter a phase and corresponding optional sequence number to determine the order in which the phase appears in the List of Values on WO Task screens. The phase with the lowest sequence number will be

Phase	Sequence No.
▲ CLOSEOUT REVIEW	45
EVENTS (PHASE 5)	25
INITIAL REVIEW (PHASE 1)	5
MATERIAL PLANNING	14
PLAN RESOURCES (PHASE 2)	10
READY FOR SCHEDULE	28
RESOURCE PLANNING	16
SCHEDULE MATERIALS (PHASE 3)	15
SCHEDULED	30
WAITING FOR EVENT	29
WAITING FOR SCHEDULE (PHASE 6)	27
WAITING MATERIALS	21
▼ WAITING MATERIALS (PHASE 4)	20

Description

Defines the planning phases of work order tasks.

Enter a phase and corresponding optional sequence number to determine the order in which the phase appears in the List of Values on Work Order Task screens. The phase with the lowest sequence number will be the default phase when new Work Order Task records are created.

Work Order Travel Time Rule

Business Rule WORK ORDER TRAVEL TIME

Rule ID: Business Parameter Limit?

Desc: This rule defines the travel time for work regions.

Comment

Work Region	Travel Time
▲ 7/11	1
BURGER KING	5
DUNKIN DONUTS	3
JACK IN THE BOX	.75
REGION 1	1.00

Description

Define travel times by region for work order tasks.

Code Tables

Code Table 12: Shop Codes

Shop field - Define codes to identify your organizations repair facilities. Since this field is included on the Search Options screen it can be used to search for vehicles being repaired.

Code Table 41: Work Priority

Priority field (second field) - Define codes that indicate the relative work or safety impact of the work that is to be done. This information is later used by the system to calculate the overall priority of work orders.

By default the system contains entries for Code Table 41. The user has the ability to alter the data in this Code Table, however we recommend that only the Description field be altered if necessary since the numeric values (1-9) are used in the calculation of Priority.

Code Table 107: Units

Meter field - Define valid names for the types of measurement units that can be metered and tracked to determine asset operation.

Code Table 190: Job Codes

Job field - Define codes to identify standard repairs. Typical entries are job codes for performing an oil change, rotating tires, replacing a fuel filter, and replacing an oil filter. The code table for the Reason field is linked to code table 190.

Code Tables 281 - 285: Report Codes 1-5

The Lists of Values for Work Order Task Report Codes reference Code Tables 281-285. Enter Code names, and code descriptions that can serve as a method of categorizing work order tasks for reporting purposes.

Code Table 660: Vehicle Reason for Repair

Reason field - Define codes for the reason to perform maintenance. This code table can be used as the linked code for code table 190, however any available code table can be used as well.

Code Table 661: Vehicle Action Taken

Action field - Define codes for the action that needs to be taken to perform maintenance on the asset.

Code Table 662: Vehicle System Codes

Vehicle Codes fields - Define VMRS (Vehicle Maintenance Reporting Standard) system codes. The first field represents "system" the second represents "assembly," and the third represents "component." The Assembly and Component fields will require that you also configure code tables 1150 and 1151 and link them to code table 662.

Code Table 1050: Precedence Relationship Code

Precedence view Relationship field - Define codes for the Relationship field on the Work Order Task Precedence view. Please note: These relationships are informational only and are not enforced by the system.

Sample codes:

FS - Finish to Start (Task B cannot start until Task A is finished)

SF - Start to Finish (Task B must be started before Task A can be finished)

SS - Start to Start (Task A and B can start concurrently)

FF - Finish to Finish (Task A and B can finish concurrently)

Work Order (Finishing Tasks)

When you set the status of a work order task to Finished, the system opens the Task Finishing Wizard to capture closeout information. The following code tables define fields in the wizard.

Code Table 9: Repair Codes (Length = 10)

Repair Code field - Define types of repair that may be done. Possible Repair Codes may include Rebuild, Replace, Require, etc.

Code Table 10: Failure Codes (Length = 10)

Failure Code field - Define types of equipment failure that may occur. Typical Failure Codes may include Corrosion, Distortion, Erosion, etc.

Code Table 51: Failure Modes (Length = 10)

Failure Mode field - Define further codes to identify failures found while work was being performed. Failure Mode is defined as “any event which is likely to cause an asset (or system or process) to fail.” Some examples would be: Deterioration, Lubrication Failure, Dirt or contamination, Disassembly, capability reducing' human error, deliberate overloading, unintentional overloading, incorrect process material, Initial incapability, etc.

Code Table 52: Root Cause Codes (Length = 10)

Root Failure Cause field - Define codes to further identify the base cause which created the failure. Some examples include: Stresses, degradation of insulation, lack of lubrication, breakdown of lubrication, Blocking, sticking, jamming, weld failure, solder failure, fatigue, corrosion, vibration, Anthropometric=cannot reach, human sensory=cannot see/smell/hear, physiological= hot/cold/loud/working too long and psychological=slip/lapse or mistake/violation. (ex: control valve left shut due to inability to get into tight space), Operator error, Under-designed, Operator error combined with under-designed, Out of specification, Desired performance is outside of assets capability, etc.

Code Table 189: Work Action Codes (Length = 8)

Further Action field - Define codes for further action required. Examples include Adjust, Align, etc.

Code Table 222: Component Category (Length = 10)

Component Code field - Define codes to identify which type of component the failure occurred on. This field can be used from the Search Options screen to narrow down searches. Component categories may include Bearings, Valves, Hose, etc.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Add Dependent Materials

Allows users to display a listing of dependent items associated with the CU highlighted on the CU Worksheet, and place a check in the Add box for items they want to include on the Items Worksheet.

Assign Contractor to CUs

Grants the ability to assign multiple compatible units to a single contractor in the CU Worksheet view of the Work Order Task module.

Cost and Closeout

Adds the Cost and Closeout action to the user's home page action list.

Create Checkout Request from WO

Grants the ability to create checkout requests by selecting an action on the Work Order Task record.

Repair Removed Part

Grants the ability to use the Repair Removed Part Action from the Work Order Task module Actions list to create a Material Disposition record.

Show CU Location

Allows users to access the CU Location and Location Worksheet views on Work Order Tasks. Users must also have the SHOW CU ON WO responsibility.

Show CU on WO

Grants the ability to use Compatible Units functionality on the Work Order Task by selecting CU Worksheet, Contractor Contributed and Item Worksheet from the Views list.

Update Reg Acct. Dist

Grants access to an action that allows the user to update override percentages on the Work Order Task module Regulatory Accounting view.

Value Assets in Prior Year

Grants the ability to execute the Value Assets in Prior Year action from the Work Order Task Construction Assets view. This action becomes available when the work order is in Finished status. If you select this action from the actions list and the fixed asset batch job (sdbp_work_order.fixed_asset) runs, the system retrieves the accounting period based on the closed date on the work order. The year where the closed date falls is lessened by one (to derive the prior year), and this year is then used to determine which year to distribute direct and indirect overhead costs.

WO Task to Active

Grants the ability to change the status of a work order task to ACTIVE.

Reports

S_RPT056 - Work Order Task Aging Report

Lists active work orders & tasks and the number of days the work order task has been backlogged. The date that the work order was activated is subtracted from the current date to determine the number of backlog days.

S_RPT041 - Daily Schedule Report

Lists the work order tasks scheduled for a selected day.

S_RPT040 - Workweek Schedule Report

Lists the work order tasks scheduled for a selected week.

S_RPT045 - Work Order Backlog Report

Summarizes active work order task information.

S_RPT055 - Work Order Backlog Detail Report

A detailed summary of active work order task information.

S_RPT043 - Work Order Tasks Delayed by Materials Report

Summarizes work order tasks and materials information for work orders requiring stock (parts) currently not available in the storeroom.

Batch Processes

Cost Asset - sdbp_cost_asset;

Allocates costs to assets indicated on the Asset list in the Work Order Task module by creating cost adjustment records and posting accordingly. This functionality is only applicable when the Allocate Costs to Asset option in the Work Order Processing business rule is set to ON. You must either set the job run option to YES in the Batch Job Control business rule or set up an individual batch schedule for it to run automatically. The cost adjustment is not created until the work order is in closed status, so this should run after the close work order process. Please refer to the instructions under the Job Manager module for more information.

Cost Adjustment for PM Route - sdbp_cost_route.cost_route;

Generates and posts cost adjustments to remove charges from the work order task account and distribute them among the PM Route's assets. Labor and material costs related to accomplishing the scheduled PM Route are charged against the work order's task and then distributed amongst the assets that were finished on the PM Route.

Cost and Closeout - smu_interface.sdbp_mu_interface;

Processes transactions entered in cost and closeout.

Cost Labor - sdbp_cost_labor.cost_labor;

Processes approved labor costs (from timesheets) that have not yet been posted. Costs are posted to the work order task as a Labor record. If a Labor Requirement record does not yet already exist for the task, the system inserts one, then posts the cost. Once a labor charge is successfully processed, it is marked as posted.

Create Change Request -**sdbp_create_change_request.create_change_req_from_wo;**

Creates change requests as a result of construction assets entered on work order tasks. Change requests are created based on the setting of the Apply Change Req Created Fr WO rule key in the Work Order Processing business rule. The change requests are created when the Work Order status is set to Finished.

Finish WO - sdbp_finish_wo;

Updates the work order header status to Finished if either all associated tasks are in Closed, Canceled, or Finished status, or if the work order has no associated tasks.

Held for Parts - sdbp_held_for_parts;

Reviews Work Order Task Parts Requirements vs. stock inventory and direct purchases for a task. If the On-Hand quantity in a storeroom is less than the amount required for an active task or if direct purchase items ordered for a task are still not received, the Held for Parts indicator on the task is checked. If all parts required (storeroom and direct purchase) are available, the Held for Parts indicator is unchecked.

Process Fixed Assets - sdbp_work_order.fixed_asset;

Processes actual amounts and allocation amounts for a work order task and applies them to the Regulatory Accounts associated to the compatible units on the task. Also determines the value of fixed assets associated to the capital regulatory accounts on the work order tasks. This procedure also includes the package that creates change requests for the creation or retirement of group assets on a work order task.

Process Service Timesheet -**sdbp_process_service_timesheet.post_approved_time;**

Processes approved labor costs (from service timesheets) that have not yet been posted. Costs are posted to the work order task as a Labor record. If a Labor Requirement record does not yet already exist for the task, the system inserts one, then posts the cost. Once a labor charge is successfully processed, it is marked as posted.

Reschedule - sdbp_reschedule.job_reschedule;

Reviews all active work order tasks which are unfinished and places them on the daily and / or weekly schedules as defined in the Auto Generate Daily Schedule and Auto Generate Weekly Schedule rules. Work orders that were generated by PM Master processing will also be placed on the appropriate schedule.

Reset Demand Quantity - sdbp_storeroom_demand;

Recalculates the On-Demand Quantity for parts within the storeroom. This procedure reviews all active work order tasks, summing the quantities required across tasks for stock items. Once recalculated, the On-Demand Quantity for each storeroom item is updated accordingly. Note that this batch procedure is not a required procedure since standard

processing maintains the storeroom On-Demand Quantity. This serves as an extra level of assurance that the On-Demand Quantities are correct as of each nightly batch run. Note that running this process could potentially be time consuming if there is a large amount of data for the system to process.

Regulatory Account Cost - `sdbp_regulatory_account_cost`;

Posts costs associated to regulatory accounts.

Work Order Labor - `sdbp_work_order_labor`;

Processes changes made to work order task labor values.

Benchmark Work Order Module

The system allows for the creation of benchmark work orders. Rules and settings for benchmark work orders are the same as those for regular work orders. Please refer to the responsibilities for Benchmark specific roles and authorities.

Work Order Business Rules also affect benchmark work orders.

Fields

Sequence No.: Benchmark Work Order No.

The record number is comprised of a unique ID (Ex. "B000138"). Benchmark Work Order record numbers must be system generated. Manual creation of these record numbers could result in critical system errors when records are created from other records or in batch procedures.

TABLE NAME - BENCHMARK - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Batch Processes

PM Cycle - sdbp_pm_cycle_job.start_job;

Reviews active PM Masters and cycles those that are due, creating work orders in the status defined in the PM Master Parameters business rule. If the PM is being cycled and the Benchmark's component is no longer installed on the Benchmark's asset, the system will generate a work order with the asset from the Benchmark and will not bring over the component.

Work Order Labor - sdbp_work_order_labor;

Processes changes made to Work Order Task labor values.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Copy Record

BENCHWO - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Create Work Order From Benchmark

Grants the ability to create a follow-up Work Order from a Benchmark Work Order record.

Crew Module

Fields

Crew Field

When new Crew records are created this field is used to define the name of the crew. This name or code will then be used on work records that reference the crew.

Business Rules

Auto Generate Daily Schedule Rule

The screenshot shows a window titled "Business Rule AUTO GENERATE DAILY SCHEDULE". It contains the following fields and controls:

- Rule ID:** A text field containing "AUTO GENERATE DAILY SCHEDULE".
- Business:** A dropdown menu with "Business" selected.
- List:** A dropdown menu with "List" selected.
- Limit?:** An unchecked checkbox.
- Desc:** A text area containing "This rule allows automatic cycling of unfinished Work Order Task(s) to the Crew's next day's schedule."
- Comment:** A text area containing "All Crews may be entered. Enter ON in the 'Generate?' column to have unfinished Work Order Task(s) cycle to Crew's next day's schedule. Enter OFF in the 'Generate?' column to have unfinished Work Order".
- Crew:** A list box containing "BYB", "PM2", "RAY", "RVM", and "RVM_1".
- Generate?:** A column of five text boxes, each containing "ON".
- Description:** An empty text area at the bottom.

Control automatic cycling of unfinished work order tasks to the crew's next day's schedule.

When the `sdbp_reschedule.job_reschedule` batch job is run, work order tasks that are in ACTIVE status are placed on the next day's schedule for that task's crew. Schedules are generated according to the days and hours entered in the Crew Daily Hours view of the Crew module.

Note: The Automatic Scheduling feature only applies to ACTIVE work order tasks. If you are using the Scheduling modules to schedule PLANNED (or non-active) work order tasks, you must manually move the work tasks to future schedules. This is due to the fact that the "completion" of a PLANNED work order task does not result in the work order task being FINISHED or CANCELED. The Automatic Scheduling option would continue to rollover the work order task to the Planners schedule until work was actually finished.

Crew / Generate

Enter any valid crew that exists in the Crew module then enter ON or OFF in the Generate column to determine whether or not the system should cycle unfinished work order tasks to the crew's next day's schedule. Any crew that is not listed will be defaulted to OFF and no schedules will be created automatically for that crew. Schedules are generated according to the days and hours entered in the Crew Daily Hours view of the Crew module.

Craft Rates Rule

Craft	Rate	Reg Expense	Prem Expense
ADMIN	25	00003	00004
APPRN	17.5	00003	00004
CARP	20	00003	00004
CUST	18.50	00003	00004
ELEC	24.50	00003	00004

Description
Admin

Define Craft codes along with associated wage rates and expense codes.

Craft

Classify job types in the Craft field. Examples are ENG for engineer or MECH for mechanic.

Rate

This parameter sets the wage rate for the Craft listed.

Reg Expense

This parameter sets the expense code that the system will charge the employee's regular (i.e. non-premium) labor charges to.

Prem Expense

This parameter sets the expense code that the system will charge the employee's premium (i.e. Overtime) labor charges to.

Code Tables

Code Table 310: Supervisor Title

Supervisor field - Define the supervisor titles to be used for various records. These codes define a supervisory position, not a specific person. Some examples of titles are Head Supervisor, Maintenance Supervisor, and Foreman.

Copy Record

CREWMOD - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Reports

S_RPT079 - Overtime Standing Report by Crew

Lists overtime standing information for each crew.

Views

Crew Daily Hours

Define the crafts and number of hours that are available to each crew. This information is used in the Daily Schedule module to determine the resources available for scheduling.

Crew ILBC2 Crew Daily Hours

Daily Hours Summary

Craft	Sun	Mon	Tue	Wed	Thu	Fri	Sat
ADMN	8	8	8	8	8	8	8
TECH	16	16	16	16	16	16	16
Total	24						

Daily Hours Data

Craft	Day	Hours
ADMN	FRIDAY	8
ADMN	MONDAY	8
ADMN	SATURDAY	8
ADMN	THURSDAY	8
ADMN	WEDNESDAY	8
ADMN	TUESDAY	8
ADMN	SUNDAY	8
TECH	FRIDAY	16

This view was added in release 6.5 to replace the Daily Hours rule key in the Schedule Labor Resources business rule.

Crew Employee Assignment

Assign Employees to the crew in the Crew Employee Assignment View.

Crew ILBC2 Crew Employee Assignment

Crew: ILBC2 Supervisor: SUFORE

Craft	Emp No	Employee Name	Employee Status	Lead
MECH	0002	Userson, Newious	ACTIVE	<input type="checkbox"/>
TECH	100	BEELER, RICHARD	ACTIVE	<input type="checkbox"/>
ELEC	101	BROWN, IMANI L.	ACTIVE	<input type="checkbox"/>
ELEC	104	Guy, New	ACTIVE	<input type="checkbox"/>
				<input type="checkbox"/>

When an Employee Number is selected, the Craft Code and Employee Name are automatically populated from the Employee module of the Resource subsystem. Only employees in 'active' status can be assigned to a crew.

Crew Activity Log Module

Fields

Crew

This field can be used to create a new crew or reference a crew that already exists. Crews can be saved directly into the crew module from this screen.

Code Tables

Code Table 110: Backlog Groups

Backlog Group field - These groups can be used to group crews or to find and categorize work orders at a high level. This code table is used in the Process, Asset, Function, Work Request, Work Order, and Crew Activity Log modules.

Code Table 110 is used in the following modules: Process, Asset, Function, Work Request, Work Order, Crew Activity Log.

Code Table 120: Crew Event Types

Event Type field - Define codes to identify stages completed by a crew in the work process. Examples include Finish (indicates finished work on a work order task), Start (identifies a started task), etc. This code table is also used in the Work Order Activity Log.

Activity Tracking Module

Fields

Sequence No.: Tracking No.

The record number is comprised of a unique ID. Users typically have the system generate this number.

TABLE NAME - SA_ACTIVITY_TRACKING - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 13: Type of Activity

Activity field - Define task activity types. Types of work might include Mowing, Drilling, Digging, Resurfacing, etc.

Code Table 14: Type of Activity Units

Units field- Define work units. Types of Units might include Kilometers, Acres etc. depending on the types of work that are defined.

Copy Record

ACTTRACK - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Fleet Asset Module

Fields

Sequence No.: Vehicle ID

The Fleet Asset record number is comprised of a unique ID (Ex. "VHC-0002"). Vehicle ID numbers are typically system generated.

TABLE NAME - FLEET - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Class

The list of values for the Class field is controlled by the Asset Class module.

Specification (More Data View)

Specification codes are defined in the Specification module.

Operational ID (Fleet Operational/Maintenance View)


The list of values for the Operational ID field is comprised of values entered in the Operational Schedule module under Fleet in the Maintenance subsystem.

Maintenance Manager

The value entered in the Maintenance Manager field on the Asset header determines which Maintenance Manager will bear the costs associated with the asset when work is done. The field is controlled by a list of values the system builds using the Maintenance Manager module in the Resource subsystem.

Business Rules

Asset Depreciation Rule



Depreciation Rule	Value
CONVENTION	FULL-MONTH
FREQUENCY	ANNUALLY
LAST PERIOD PROCESSED	200412
LAST RUN DATE	09-FEB-05

This rule determines how the system will process asset depreciation costs and post them to the account log.

Once the values for the Convention and Frequency rule keys are set and the depreciation batch job has run, the settings should not be changed. Any modification will result in irreversible errors in your depreciation calculations.

CONVENTION - Select Full-Month to indicate the amount of depreciation that can be claimed in the year the asset is placed in service. Full-Month is the only option.

FREQUENCY - The value entered here determines how often all asset's depreciation will be written to the account log. For example, if the Last Processed Date is '200301' and the frequency is monthly, the account log will have entries of '01 2003' and in the future, the following months (i.e. 02 2003, 03 2003). Valid frequencies are Monthly, Quarterly or Annually.

LAST PERIOD PROCESSED - The Administrator should enter an initial date in this field when the rule is configured. Once the date is set the system updates the date when the account depreciation batch process runs. Do not modify this rule key after initial configuration.

The proper date format is YYYYMM.

LAST RUNTIME DATE - Last Run Date will be updated by the system whenever the batch procedure runs.

Asset Key Segments Rule

Segment	Label	Length	Option
SEGMENT1	General	4	Y-
SEGMENT2	Street Number	4	Y-
SEGMENT3	Node Number	5	Y-
SEGMENT4	Lateral Number	3	Y-
SEGMENT5	Sequential Number	6	Y-

The Asset Key Segments business rule defines the Asset Key Flex Segments to customize Asset IDs. Each segment contains a label, length and options.

For more information regarding this feature, please refer to the Asset section of the Resource User Guide.

This functionality allows users to group Asset IDs to make it easier to locate the required asset. Since the system allows an infinite number of Asset IDs to be defined, Asset Key Segments can significantly aid in searching through very large databases.

To disable this Rule, the label field for SEGMENT1 must be null. If the rule is disabled, the Segments view does not appear in the Asset or Fleet Asset module, and the associated functionality is turned off.

Segment

The “SEGMENT” column determines which segment, or “piece”, of the Asset ID is being defined.

Label

The “LABEL” column describes the SEGMENT. It is the label displayed within the Asset module windows.

Length

The “LENGTH” column defines the maximum number of characters for the SEGMENT.

Option

The first character in the “OPTION” column indicates whether a code table is to be used: “Y” for YES, “N” for NO. The second character in the “OPTION” column is the delimiter for the SEGMENT.

To make any one SEGMENT a required field, use the Modules Administration - Forms module. You can also configure Special LOVs for these fields.

Downtime Type By Work Type

Business Rule DOWNTIME TYPE BY WORK TYPE

Rule ID: DOWNTIME TYPE BY WORK TYPE Business Parameter Limit?

Desc: This rule is used to establish what type of Downtime will charged against a Fleet Asset based on the Work Order Type. The two options are Planned or Unplanned.

Comment: Defines Downtime Type by Work Order Type.

Work Order Type	Downtime Type
E	UNPLANNED
P	PLANNED
R	PLANNED
S	UNPLANNED
U	UNPLANNED

Description: Emergency Work Order

This business rule is used to establish what type of downtime will charged against a Fleet Asset based on the Work Order Type. The two options for downtime type are Planned or Unplanned. Example: Work Type = E, Downtime type = Unplanned

Fleet Constants Rule

Business Rule FLEET CONSTANTS

Rule ID: FLEET CONSTANTS Business Parameter Limit?

Desc: This rule defines the "constants" for Fleet related modules.

Comment:

Constant Field	Value
METER_UNIT	Miles

Description: Defines meter units label to be used in fleet related modules; e.g. Miles, Kilometers.

Define the unit type to use in Fleet related modules. If this Business Rule is not configured the default will be the value that was previously hard coded in the forms.

Constant Field and Value

Enter the desired value for meter units in Fleet modules ; e.g. Miles, Kilometers. The list of values for the Value field references Code Table 107.

Fleet Mileage Reasonability Rule

Business Rule FLEET MILEAGE REASONABILITY

Rule ID: Business Limit?

Desc: This rule is used by the Fleet Mileage Reasonability report which identifies those vehicles which have exceeded their expected mileage in a given period.

Comment: CLASS / PERIOD
"CLASS" corresponds to the vehicle fleet classes set up in Code Table 11. "PERIODS" are defined as

Class	Period	Mileage
1AB0	YEAR	27500
2AA1	MONTH	2500
2AC1	MONTH	200
2AC1	QUARTER	400

Description:

This rule establishes criteria used on the Fleet Mileage Reasonability report which identifies vehicles that have exceeded their expected mileage in a given period.

This report can be accessed by selecting Vehicles Exceeding Mileage Limits from the Search screen in the Fleet Asset module.

Class

Class corresponds to the vehicle fleet classes set up in the Asset Class module.

Period

Periods are defined as Year, Quarter, and Month. The list of values attached to this column has each of the vehicle classes from the Asset Class module combined with YEAR, QUARTER and MONTH.

Mileage

This column defines the mileage limit for vehicles. When vehicles exceed this mileage in a time period, they are reported on the Fleet Mileage Reasonability Report. This report can be accessed from the Actions list on the Fleet Asset Search Options screen.

Planner Rule

Code	Full Name	Username
123456	Max Length	BYB_USER_1
BYB1	Branwen Y. Burgess	BRANWEN
RLW	Ray Winther	RAY
RVM	Raya Veksler	RVEKSLER
SRP	sudha's	SREDDY
WWW	Nolan and Lauren's D	WILLY

Define planner codes, and identify the full names and usernames associated to each code. These codes are used when identifying a planner on work records.

The user associated with the code receives an alert when an event occurs where an alert would be sent to the planner. For example, when a planner plans parts against a work order and needs to be notified when the parts have arrived. This does not mean that the system is configured to send alerts regarding any record where a planner is indicated.

Code

Enter the codes for planners in the Code column. Each code must be unique.

Full Name

Enter the full name of the person associated with the code. A person can be listed on more than one code.

Username

Enter the username of the person associated with the code. Since a person can be listed on more than one code, the username can be listed more than once as well.

Batch Processes

Depreciate Assets - sdbp_end_period_depreciation;

Depreciation costs are posted by batch according to settings in the Asset Depreciation Business Rule.

Code Tables

Code Table 38: Drive Types (More Data View)

Drive Type field - Define values for vehicle capabilities. Typical entries are 4x4 and 2x4. This field is searchable from the Search Options screen.

Code Table 39: Fuel Types (More Data View)

Fuel Type field - Define codes for vehicle fuel requirements. Typical entries are Propane, Leaded, Unleaded, and Diesel.

Code Table 40: Criticality Codes

Criticality field - The criticality number represents the relative work or safety impact of

the fleet asset. This number is later used by the system to calculate the overall priority of work orders.

The system contains default entries for Code Table 40, however, you can alter the data. We recommend that only the Description field be altered if necessary since the numeric values (1-9) are used in the calculation of priority on work orders and work requests.

Code Table 12: Shop Codes

Shop field - Define codes to identify your organizations repair facilities. Since this field is included on the Search Options screen it can be used to search for vehicles being repaired.

Code Table 25: Building Codes

Building field - Define building identifiers for the fleet asset location specific to your organization. The Building field is searchable from the Search Options screen, and can be useful in finding fleet assets when only the building location is known.

Code Table 67: Vehicle Make

Make field - Define codes to further describe vehicles by Make. Typical Vehicle Makes are Ford, Chevy, Toyota, etc. for Passenger Vehicle or Caterpillar for Industrial Vehicle. Vehicle Make is one of the search criteria on the Fleet Asset Search Options screen.

Code Table 510: Vehicle Organization

Organization field - Define codes to indicate which part of your organization the vehicle belongs to, or any other logical definition you would like to use for this field. This field is searchable from the Search Options screen.

Code Table 511: Vehicle Sub-Organization

Sub-Org field - You can use this code table to further define your vehicles according to your business practices. This field is searchable from the Search Options screen.

Code Table 512: Monitoring Group (Fleet Operational/Maintenance View)

Monitoring Group field - Define codes for the group responsible for ensuring that required maintenance is performed on the vehicle.

Vehicle Model Code Tables

Model field - Define codes to further describe vehicles by Model. There are a series of user setup code tables that are linked to Code Table 67 for Vehicle Make. As an example, if the vehicle (Fleet Asset) is a Ford F-150 Pickup truck, Code Table 67 would contain Ford, with a link to another Code Table (ex: 3000) where Code Table 3000 contains all the Make codes for Ford vehicles. In this example, Code Table 3000 would contain at least "F-150" as a value. The Vehicle Model code is only searchable from the Fleet Asset Search Options if the Vehicle Make has already been selected and the Vehicle Make selected has a Model listed in the code table that it's linked to.

Copy Record

FLTASSET - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more

information.

Create Activity Log From Asset

Grants the ability to create an asset activity log entry using the action on the Asset record.

Create Emergency WO Fleet Asset

Grants the ability to create an Emergency Work Order by selecting the action on a Fleet Asset record.

Create Work Order Fleet Asset

Grants the ability to create a Work Order record by selecting the action on a Fleet Asset record.

Create Work Request Fleet Asset

Grants the ability to create a Work Request record by selecting the action on a Fleet Asset record.

Reports

S_RPT075 - Equipment History Summary Report

Lists Vehicle maintenance and operating history.

S_RPT077 - Equipment List by Shop Report

Provides an equipment listing by shop for fleet assets and includes acquisition date, depreciation value, and runtime information.

S_RPT076 - Historical Cost Performance Report

Lists historical cost performance for fleet assets.

S_RPT073 - Mechanic Accountability Report

Provides labor distribution per mechanic per shop per sub shop for fleet assets.

Fleet Work Order Module

Fields

Sequence No.: Fleet Work Order No.

The Fleet Work Order record number is comprised of a unique ID (Ex. "01007776"). Fleet Work Order record numbers must be system generated. Manual creation of these record numbers could result in critical system errors when records are created from other records or in batch procedures.

TABLE NAME - SA_WORK_ORDER - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 3: Maintenance (Length = 10)

Class/Catg. field (second field) - Define categories describing types of work. The Maintenance Category field can be searched Fleet Work Order Search Options screen.

Code Table 2: Maintenance Classes (Length = 10)

Class/Catg. field (first field) - Define classes describing types of work. The Maintenance Class field can be searched on the Fleet Work Order Search Options screen.

Code Table 12: Shop Codes (Length = 10)

Shop field - Define codes to identify your organizations repair facilities. Since this field is included on the Search Options screen it can be used to search for vehicles being repaired.

Code Table 41: Work Priority Codes (Length = 1)

Priority field (second field) - Define codes that indicate the relative work or safety impact of the work that is to be done. This information is later used by the system to calculate the overall priority of fleet work orders.

By default the system contains entries for Code Table 41. The user has the ability to alter the data in this Code Table, however we recommend that only the Description field be altered if necessary since the numeric values (1-9) are used in the calculation of Priority.

Code Table 107: Meter Units (Length = 15)

Meter field - Define valid names for the types of measurement units that can be metered and tracked to determine asset operation.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Create Checkout Request from WO

Grants the ability to create checkout requests by selecting an action on the Work Order Task record.

Log Fleet Downtime

Grants the ability to select Log In/Out as Downtime from the Actions list on the main Fleet Work Order record. The action records in/out times and calculates the downtime based on the operational schedule for the asset.

Repair Removed Part

Grants the ability to use the Repair Removed Part action from the Fleet Work Order Task module Actions list to create a Material Disposition record.

Update Benchmark Work Order

Grants access to the action which allows the user to update a benchmark fleet work order with information from a fleet work order that was generated from a PM Master.

Update WO from Benchmark

Grants access to the action which allows the user to update a fleet work order with information from a fleet benchmark work order record.

Fleet Work Order Task Module

Fields

Permit Types LOV (Work Order Permit View)

Permit Types, defined in the Permit Types Business Rule, can be selected in this field to identify the Permits that will be required for this work order task. After a Permit Type is identified on this view, “red” Permit text will be displayed on the work order header once the work order is set to Active status, if the Permit Text Business Rule is set to ON.

Code Tables

Code Table 190: Job Codes (Length = 10)

Job field - Define codes to identify standard repairs. Typical entries are job codes for performing an oil change, rotating tires, replacing a fuel filter, and replacing an oil filter. The code table for the Reason field is linked to code table 190. Any available user code table can be used to define the reason field. Code table 660 is recommended.

Code Table 281 - 285: Report Codes 1 - 5 (Length = 10)

The Report Codes fields can be used to classify and generate reports. You can populate these Code Tables with items such as PM, Major Repairs, Accident, and so on. This grouping serves as a method of categorizing fleet work orders for reporting purposes.

(Optional) Code Table 660: Vehicle Reason for Repair (Length = 10)

Reason field - Define codes for the reason to perform maintenance. This code table can be used as the linked code for code table 190, however any available code table can be used as well.

Code Table 661: Vehicle Action Taken (Length = 10)

Action field - Define codes for the action that needs to be taken to perform maintenance on the asset.

Code Table 662: Vehicle System (Length = 3)

System field - Define VMRS (Vehicle Maintenance Reporting Standard) system codes. The Assembly and Component fields will require that you also configure code tables that are linked to code table 662. Suggested code tables to use are 1150 and 1151, but it is not required that you use these.

Code Table 1150: Vehicle Assembly (Length = 3)

Assembly field - Suggested code table to link to CT 662 for the Assembly field. Enter VMRS codes for assembly. If you do not use VMRS these codes can also be configured according to your business practices.

Code Table 1151: Vehicle Component (Length = 3)

Component field - Suggested code table to link to CT 662 for the Component field. Enter VMRS codes for components. If you do not use VMRS these codes can also be configured according to your business practices.

Fleet Benchmark Work Order Module

Fields

Sequence No.: Fleet Benchmark Work Order

The Fleet Benchmark Work Order record number is comprised of a unique ID (Ex. “B000086”). Fleet Benchmark Work Order record numbers must be system generated. Manual creation of these record numbers could result in critical system errors when records are created from other records or in batch procedures.

TABLE NAME - BENCHMARK - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

PM Fleet Type	Benchmark No.
BYB1	B000047
BYB2	B000129
BYB_MAX_FLEET_PM_TYPE234567890	B000047
CAK1	B000006
ILBV1 OILCHNGE	B000032
MAW	B000130
QBP_1	B000122
SLC1	B000045

Copy Record

BENCHFLT- COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Reservations/Motorpool Module

Fields

Sequence No.: Reservation No.

The record number is comprised of a unique ID (Ex. "0000000003"). Fleet Reservation numbers are typically set to be system generated.

TABLE NAME - SA_FLEET_RESERVATIONS - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 24: Rental Types (Length = 10)

Rental Type field - Define codes to identify the type of rental. Typical codes include Daily, Weekly, Monthly, Yearly, etc. to represent a charge period.

Reports

S_RPT072 - Reservation Dispatch Report

Lists information check past due motorpool Reservations daily. This information is retrieved from the Reservation/Motorpool module under Fleet in the Maintenance subsystem.

Operational Schedule Module

Fields

Sequence No.: Operational ID

The Operational Schedule record number is comprised of a unique ID (Ex. "01007776"). Operational ID numbers are typically set to be user entered.

TABLE NAME - SA_OPERATIONAL_SCHEDULE - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 570: Hour

Define hourly increments that are applicable to the schedule.

Code Table 571: Minute

Define minute increments that are applicable to the schedule.

Code Table 710: Week Days

Define the days of the week that are applicable to the schedule.

Copy Record

OPERSCHD - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Permit Template Module

Use this module to track permits needed for certain types of work. Permits are usually required by outside regulation demanding creation of an audit trail to show proper procedures were followed. For example, working with hazardous materials typically requires permits indicating that the person doing the work has been trained and certified, that isolation procedures were followed, etc. Any documents attached to the Permit Template record (i.e. MSDS, Drawings, or other electronic documents) will be copied over to assets and permits that reference the Permit Template.

Fields

Sequence No.: Template ID

The Permit Template record number is comprised of a unique ID (Ex. "TMP006"). Permit Template numbers are typically set to be created manually.

TABLE NAME - SA_PERMIT_TEMPLATE - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Checklist Title - User Defined Code Table

The selections of Checklist Title(s) displayed in this field on the Permit Template, are validated against the Permit Type selected for each Permit Template.

Checklist Titles are first created in a User-Defined Code table, and then associated with the Permit TYPE in the Permit Type Business Rule.

Only those Checklists Titles, associated with the selected Permit Type will be displayed as selections in the Template Checklist Title field.

Checklist Description - User Defined Code Table

The selection of Checklist Descriptions displayed in this field on the Permit Template, are validated against the Permit Type and Checklist Title selected for each Permit Template.

Checklists are first created in a User-Defined Code table, and then associated with the Permit TYPE in the Permit Type Business Rule.

Only those Checklists Descriptions, associated with the selected Permit Type and Checklist Title, will be displayed as selections in the Template Checklist Description field.

Duration - User Defined Code Table

This field establishes the LOV for the Duration (time) field on a Permit, indicating how long the Permit remains active after the date and time in the Start field. The Duration Code Table listed on the Permit Type Business Rule is a User Defined Code Table that contains values for duration.

Copy Record

PERMTMPL - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Permits Module

Fields

Sequence No.: Permit No.

The record number is comprised of a unique ID (Ex. "PER0000075"). Permit record numbers are typically set to be system generated.

TABLE NAME - SA_PERMIT - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Approval Route Field

Designate Approval Titles for Permit records in the Approval Limit module under Approvals and Routes in the Administration subsystem.

Code Tables

Code Table 8: Permit Cancel Codes (Length = 10)

Cancel dialog box - Define reason codes for canceling permits that have been previously been created for expected work. This code table is attached to the "Please enter the reason for canceling this Permit:" field which pops up when you change the status of a permit to Canceled. Some examples of data are: Confined space not entered, duplicate permit, flooded, hazard encountered, inclement weather, work order task canceled etc.

Code Table 62: Current Position

Current Position field - Create codes to indicate possible positions for tag points.

Business Rules

Permit Type Rule

Type	Allow	Checklist	Qual Table	Eq
CDL	ALLOW	2102	2202	22
CONFINED	ALLOW	2103	2202	22
HAZMAT	ALLOW	2102	2202	22
HOT	ALLOW	2104	2202	22
LOCK	ALLOW	2101	2202	22
SAFE	ALLOW	2100	2202	22
SAFETY	ALLOW	2100	2202	22

Description
Commercial Drivers License

Define the types of permits used in the system. You can also associate each permit type to user-defined code tables listing the Permit Checklist(s), Qualification(s), Special Equipment, and Duration values.

Type

The values entered in the Type column are used to define the different categories, or types of permit templates and permits utilized at your facility. Typical Permit Types are Excavation, Easement, Hazardous Material, Hot Work, and Confined Space.

Note: If you enter types that duplicate the first 4 characters of a word (for example Safe vs. Safety), actions that call permit reports, such as Print Permits w/Document, generate with duplicate entries in the Actions list for permit records of those permit types.

Allow

Enter ALLOW or DISALLOW to designate valid Permit Types. ALLOW will designate the Permit Type is valid, and entering DISSALLOW will make the Type code invalid for future use on Permits and Permit Template records.

Checklist

Enter the User-defined Code Table number that defines the Checklist you wish to associate to the Permit Type value.

Qualifications

Enter the User-defined Code Table number that defines the Qualifications you wish to associate to the Permit Type value. NOTE: Note: If the client wishes to link a specific employee to a Qualification on a Permit record, the Employee field LOV associated with the Permit Qualification will only list those Employees whose Training record Course (Code Table 45) matches the Qualification exactly (including spelling).

Special Equipment

Enter the User-defined Code Table number that defines the Special Equipment you wish to associate to the Permit Type value.

Duration

Enter the User-defined Code Table number that defines the Duration criteria you wish to

associate to the Permit Type value.

Tag Pt Ctrl

If the value in this column is set to YES for the selected permit type, tag point processing will apply for permits of that type. If the value is set to NO, tag point processing does not apply, and the statuses, views, and options in the Permit module will be adjusted accordingly to exclude this processing.

Permit Processing Rule

The screenshot shows the configuration window for the Business Rule PERMIT PROCESSING. It includes fields for Rule ID (PERMIT PROCESSING), Business, Parameter, and Limit?. The description is "Defines Tag Point Control features." The control table is as follows:

Control	Option Status
ALLOW TAG POINT UPDATE	YES
USE TAG POINT CONTROL	YES

The description at the bottom states: "When this rule key is set to Yes, a user with the proper Responsibilities set up is allowed to delete or modify Tag Point records in the Permit module. When it is set to NO, the user is not allowed to update the Tag Point detail".

Define Tag Point control features.

Control and Option Status

ALLOW TAG POINT UPDATE - If this rule key is set to YES, the user is allowed to update the entire Tag Point detail records in the Permit module. When it is set to NO, the user is only allowed to update the Tag Point status, current position and personal protection card(s) fields.

USE TAG POINT CONTROL - This rule key was made obsolete in release 1.7.15 and will be removed in a future release. It was replaced by the Tag Pt Control option in the Permit Type business rule.

Attachment Printing Rule

The screenshot shows the configuration window for the Business Rule ATTACHMENT PRINTING. It includes fields for Rule ID (ATTACHMENT PRINTING), Business, Parameter, and Limit?. The description is "This rule turns attachment-printing with templates ON or OFF for specific modules." The comment is "The template adds a header and footer to each page. The header and footer contain supplemental information, such as page numbers and document id numbers." The module table is as follows:

Module	Use Template?
PERMITS	NO

The description at the bottom states: "Print permit attachments using Microsoft Word template?".

Indicate whether or not a template should be applied when Permit records are printed.

Module and Use Template?

Currently this option is only available in the Permit module. Indicating YES will cause the documents to print with the additional header and footer information from the template.

Copy Record

PERMIT - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Add Tag Points

Grants the ability to add Tag Points to a Permit record.

Permit to Active

Grants the ability to activate a Permit record.

Release All

Grants the ability to change all tag point statuses to Released.

Tag All

Grants the ability to change all tag point statuses to Tagged.

Verify All

Grants the ability to change all tag point statuses to Verified.

Reports

S_RPT098 - Confined Space Report

Generates a permit check list for Confined Space type permits and can be taken into the field to track the following: safety guidelines, hazards, isolation points, specification readings, and authorized signatures.

S_RPT101 - Confined Space Report [Blank]

Generates a generic Confined Space Permit that can be printed multiple times to track permit information and signatures. This is not a true report as the contents are not related to templates found in the Permit Templates module. This report acts more as a worksheet that is typically used by clients that are not using the Permits module.

S_RPT099 - Hot Work Permit Report

Generates a permit check list for Hot Work type Permits and can be taken into the field to track the following: Hazards, isolation points, specification readings, and authorized signatures.

S_RPT102 - Hot Work Permit Report [Blank]

Generates a generic Hot Work Permit that can be printed multiple times to track permit information and signatures. This is not a true report as the contents are not related to

templates found in the Permit Templates module. This report acts more as a worksheet that is typically used by clients that are not using the Permits module.

S_RPT113 - Lockout Tagout Report

Lists Asset Data and Lockout Authorizations for Permits.

S_RPT100 - Safety Work Permit Report

Generates a permit check list for Safety Work type Permits and can be taken into the field to track the following: safety guidelines, hazards, isolation points, specification readings, and authorized signatures.

Tag Point Module

Fields

Sequence No.: Tracking No.

The record number is comprised of a unique ID. Users typically have the system generate this number.

TABLE NAME - SA_TAG_POINT - The record number is comprised of a unique ID. Tag Point numbers are typically set to be created manually.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 1193: Tag Point Category

Category field - Define categories to classify tag points.

Code Table 25: Building Codes

Building field - Define codes for asset locations specific to the client organization. The Building field is searchable from the Search Options screen, and can be useful in finding assets when only the building location is known.

Code Table 61: Source Type

Source Type field - Define the type of equipment which needs to be adjusted prior to working on a designated area. Examples of data are: Upstream Breaker, Downstream Breaker, Upstream Valve, Downstream Valve.

Code Table 62: Positions for Isolation

Lockout Position and Release Position fields - Define lockout or release positions such as OFF, ON, OPEN or CLOSED.

Functions


Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Create Tag List

Grants the ability to create a tag list from tag points in the Tag Points module. The action is only available on the Results of Search screen.

Permit Processing Business Flow

The following diagram illustrates the relationship between the views and modules involved in permit processing when tag point processing functionality is in use.



Tag List Module

Fields

Sequence No.: Tracking No.

The record number is comprised of a unique ID. Users typically have the system generate this number.

TABLE NAME - SA_TAG_LIST - The record number is comprised of a unique ID. Tag List numbers are typically set to be created manually.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Copy Record

TAGLIST- COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Associate Tag List

Grants access to the action available in the Associated Assets view of the Tag List module. The action allows users to associate the tag list to an Asset record.

PM Master Module

Fields

Sequence No.: PM Master No.

The PM Master record number is comprised of a unique ID (Ex. “000029”). PM Master record numbers are typically system generated.

TABLE NAME - SA_PM_MASTER - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 198: PM Categories

PM Category field - Define classification and searchability codes for PM Masters.

Code Table 107: Units

Meter Units field (unlabeled next to Interval field on Run-Time PMs) - Define valid names for the types of measurement units that can be metered and tracked to determine asset operation.

Code Table 108: Event Groups

Event Group field - Define valid values to categorize PM Masters into logical groups. For example, all PMs that should cycle in the Winter may be in the group ‘Winter’ or all PMs involved in a major shutdown would be in the group ‘Major.’ The Event Groups field only appears on Event Type PM Masters (defined in the Schedule Basis field). Set the group to make the PM available under that group type in the PM Event module.

Code Table 109: Event Types

Event Type field - Further define Events by type. For example, PMs that should cycle in the Winter that are related to snow removal could be called “Removal”. The Event Types field only appears on Event Type PM Masters (defined in the Schedule Basis field).

Business Rules

Default Backlog Groups Rule

The screenshot shows a configuration window titled "Business Rule DEFAULT BACKLOG GROUPS". It includes fields for Rule ID, Desc, and Comment. Below these are two columns: "Crew" and "Backlog Group", each with a list of items. A "Description" field is at the bottom.

Crew	Backlog Group
BYB	BYBBLG
CAK1	CAKBLG
DP1	DEPOT1
GE	CAKBLG
LAB	BYBBLG
MASON	DEPOT1
RJB	RJBBLG
RVM	RVMBLG

Build a relationship between crews and backlog groups (sometimes called backlog crews) for Work Requests, Work Order Tasks, Benchmark Work Order Tasks, PM Masters, and on schedules.

An example of how the concept of a backlog crew may be used is that Crew A (Crew) works 1st shift and Crew B (Backlog Group) works 2nd or 3rd shift and takes on any unfinished tasks originally scheduled for Crew A (Crew) on 1st shift.

Crew and Backlog Group

Enter the crews and the associated Backlog Groups for each in the appropriate columns.

PM Master Parameters Rule

The screenshot shows a configuration window titled "Business Rule PM MASTER PARAMETERS". It includes fields for Rule ID, Desc, and Comment. Below these is a table with "PM Master Parameters" and "Values". A "Description" field is at the bottom.

PM Master Parameters	Values
ALLOW_SEASONAL_ADJUSTMENTS	YES
BENCHMARK_ASSET_CRITICALITY	YES
CYCLE_LEAD_TIME	7
INITIAL_WO_PHASE	INITIAL REVIEW (PHA
INITIAL_WO_STATUS	ACTIVE
PRIOR_YEARS_FOR_EST_VS_ACTUALS	2
RESET_CANCELED_PM_GROUP	YES
SCHEDULE_TYPE	DAILY
WORK_DAY_INCREMENT	3

Control parameters used by batch processing when cycling PM Masters.

PM Master Parameters and Values

ALLOW_SEASONAL_ADJUSTMENTS - When this parameter is set to YES, PM Master schedule dates can be calculated based on seasonal intervals defined in the PM Seasonal Adjustment business rule. When this parameter is set to NO, The Seasonal Adjustments

view in the PM Master module is not available.

BENCHMARK_ASSET_CRITICALITY - Used to determine whether the Asset Criticality is pulled from the benchmark work order or the Asset record when a work order is generated from a PM Master cycle. This capability addresses a situation where an asset has multiple Criticality values depending on the nature of the work being performed.

When the Key Value is set to YES, the Asset Criticality is always pulled from the Benchmark Work Order record.

When the Key Value is set to NO, the Use Asset/ Component from Benchmark indicator on the PM Master determines whether the Asset Criticality is pulled from the Benchmark or the Asset record.

CYCLE_LEAD_TIME - Determines the number of days before a PM is due that the system generates a work order. This allows planners and schedulers the time they need to prepare before the work actually comes due.

INITIAL_WO_PHASE - This phase defines the phase that the work order task is set to when PM Cycle batch is run. Phases are defined in the Work Order Task Planning Rule.

INITIAL_WO_STATUS - The status the work order is created in when cycled by batch. Valid options are PLANNING and ACTIVE.

PRIOR YEARS FOR EST VS ACTUALS - This rule key determines the number of years prior to the current year to use when retrieving closed Work Orders on PM Master Material and Labor Estimate views. For example, entering a 1 will calculate the estimates with Work Orders closed in the current calendar year and last calendar year, entering a 2 will calculate the estimates with Work Orders closed in the current calendar year and the prior two calendar years and so on. Entering a value of 0 will calculate the estimate with only Work Orders closed in the current calendar year. Leaving the value column empty will calculate the estimate with all closed Work Orders, regardless of when they were closed.


SCHEDULE_TYPE - Determines on which schedule the PM Work Order records generated should be placed. Valid options are DAILY and WEEKLY.

Note: Further options for daily and weekly schedules are available in the Auto-Generate Daily Schedule , Auto-Generate Weekly Schedule and Work Week business rules.

WORK_DAY_INCREMENT - Limits the number of times the system tries to locate a working day (not a weekend or holiday) to schedule the work order. An example might be when you enter the next schedule date for a PM designed to cycle on the last working day of the month. If that day is the 31st (a Sunday), the system reviews the previous day to see if it is a valid working day. This continues until the number of attempts defined here is reached. The last day of the month is then selected as the next schedule date.

RESET CANCELED PM GROUP - This option determines scheduling of lesser PM Masters in a PM Group when a higher level PM cycles, superseding the lesser PMs, but then the higher level PM Work Order is canceled or rejected. When this option is set to NO, canceling or rejecting the higher level PM Work Order simply cancels all PMs in the group and resets them to cycle on the next schedule date or runtime trigger. If this option is set to YES, canceling or rejecting the higher level PM Work Order cancels only the higher PM and all superseded PM Masters within the group are reset to cycle as previously forecast before the higher level PM cycled. If the YES setting is used, it is strongly recommended that the current meter reading field on PM Master be configured as a status required field at Finished to ensure accurate runtime forecasting. The default setting is NO.

PM Schedule Basis Rule



PM Schedule Basis	Option Status
CALENDAR_A	ALLOW
CALENDAR_I	ALLOW
EVENT	ALLOW
F_RUN-TIME	ALLOW
RUN-TIME	ALLOW

Configure the types of PM schedules available. There are several different schedule basis settings for PM Masters available within the system. They control the type of cycling information entered on a PM Master.

PM Schedule Basis

CALENDAR_A - Stands for Calendar Anniversary. Cycling of the PM Master happens at the same time period each week, month, or year. An example might be cycling the PM Master on the 15th of each month. There are more specific processing rules associated with this schedule basis.

CALENDAR_I - Stands for Calendar Interval . Cycling of the PM Master happens at the same time increment. An example might be cycling the PM Master once every two weeks. Again, there are more specific processing rules associated with this schedule basis.

EVENT - Causes Event-based PM Masters set up to cycle each time a specified event occurs, such as a shutdown. There are specific processing rules associated with this schedule basis.

F_RUN-TIME - Run-Time Interval: PM Masters to cycle based upon a Fixed Interval Runtime.

RUN-TIME - Causes Run-time based PM Masters to cycle based upon meter readings taken for the listed asset number. This might be by number of starts/stops, number of hours running, and so on. There are more specific processing rules associated with this schedule basis.

Option Status

Set the option status for a schedule basis to **ALLOW** or **DISALLOW** to use or not use that basis in the PM Master module.

PM Seasonal Adjustments Rule

Business Rule PM SEASONAL ADJUSTMENTS

Rule ID: Business Limit?

Desc:

Comment:

Season	Start Month	Start Day	End Month	En
AUTUM1	09	01	12	31
AUTUM2	11	01	11	30
AUTUM_ACTUAL	09	22	12	21
SPRING1	03	01	04	30
SPRING2	03	01	05	31
SPRING_ACTUAL	03	22	06	21
SUMMER1	05	31	09	30
SUMMER2	07	01	07	31
SUMMER3	09	01	09	30
SUMMER_ACTUAL	06	22	09	21
WINTER1	11	01	02	25
WINTER2	10	01	03	31
WINTER_ACTUAL	12	22	03	21

Description:

Do not overlap the start or end dates of seasons. If you do, the system will write an error to the Job Manager Log and use the interval on the PM Master header until the overlapping dates are corrected.

This rule defines the seasonal periods that can be used for adjusting PM Master schedule intervals. For each season you need to define, enter a season name, start month and day and end month and day. All months and days must be entered using a two character format (01-12 for months, 01-31 for days).

Batch Processes

PM Cycle - `sdbp_pm_cycle_job.start_job`;

Cycles active PM Masters that are due; creating work orders in the status defined in the PM Master Parameters business rule. If the PM is being cycled and the Benchmark's component is no longer installed on the Benchmark's asset, the system will generate a work order with the asset from the Benchmark and will not bring over the component.

PM Finish - `sdbp_pm_finish`;

Processes PM Master information for those PMs where the associated work order has been set to Finished status. This includes entering the work completion date, inserting a new Forecast record (to maintain the correct number of future Cycles), and setting any skipped Forecast dates to Canceled status. The next schedule date is recalculated (for Calendar Interval PMs) and is placed on the PM Master record.

PM Routing - `sdbp_pm_routing`;

Updates PM Stops based upon the Completed Dates entered on a scheduled PM route list. Next schedule dates are then adjusted as required and the PM route stop item is set to Posted status.

Copy Record

PMMASTER- COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer

to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Cancel PM Master Backlog

Grants the ability to cancel forecasted backlog on the PM Master Forecast view.

Credit PM

Grants the ability to use one work order to credit multiple PM Forecasts from PMs that may not have created the original work order.

Show Cycle This PM Now Action

Allows users to access the Cycle this PM Now action in the PM Master module.

Show Cycle PM Group Now Action

Allows users to access the Cycle this PM Group Now action in the PM Master module.

Update Estimate Hours

Grants access to the action which allows the user to update Benchmark Work Order Estimates with the average from historical hours.

Update Estimate Quantity

Grants access to the action which allows the user to update Benchmark Work Order Estimates with the average from historical usage.

Reports

S_RPT090 - PM By Asset Report

Lists the PM Masters and subordinate PM Masters by asset.

S_RPT074 - Preventive Maintenance Report

Lists information to schedule vehicles for PM's on a monthly basis.

Charts

S_CHT124 - Corrective vs. Preventive Work Orders

A comparison of Corrective Work Orders to Preventive Work Orders for the current year and the previous year. The data can be filtered further by Plant, Department and Area. Other filtering options, including Department, Area and Asset, are available in the Chart Field List.

S_CHT142 - Late PMs for Safety Equipment

The number of late PMs for safety equipment to total PMs for safety equipment, for the current year and the previous year. An asset is considered to be "safety equipment" if the Safety Critical indicator on a Work Order Task record is checked. The data can be filtered by plant. Other filtering options, including Department, Area and Asset, are available in the Chart Field List.

S_CHT143 - Late Preventive Maintenance Work Orders

A comparison of the number of Late PMs to Total PMs for the current year and the

previous year. The data can be filtered by plant. Other filtering options available in the Chart Field List include Department, Area and Asset.

S_CHT164 - PM Forecast Months

The number of PM Work Orders forecasted for the current year and the next five years. The data can be viewed by Year, Quarter and/or Months. The data can be filtered further by Plant and Crew.

S_CHT129 - PM Forecast Months - Estimated Duration

The number of PM Work Orders forecasted for the current year and the next five years. The data can be viewed by Year, Quarter and/or Months. The data can be filtered further by Plant and Crew.

S_CHT130 - PM Forecast Weeks

The number of PM Work Orders forecasted for the current year and the next five years. The data can be viewed by Year and/or Weeks. The data can be filtered further by Plant and Crew.

S_CHT165 - PM Forecast Weeks - Estimated Duration

The estimated duration of Preventive Maintenance Work Orders forecasted for the current year and the next five years. The data can be viewed by Year and/or Weeks. The data can be filtered further by Plant and Crew.

S_CHT131 - PM History Months

The number of Preventive Maintenance Work Orders that were scheduled for the current year and the previous five years. The data can be view by Year, Quarter and/or Months. The data can be filtered further by Plant and Lead Crew. Other filtering options, such as Department and Area, are available in the Chart Field List.

S_CHT132 - PM History Weeks

The number of Preventive Maintenance Work Orders that were scheduled for the current year and the previous five years. The data can be view by Year and/or Weeks. The data can be filtered further by Plant and Lead Crew. Other filtering options, such as Department and Area, are available in the Chart Field List.

S_CHT146 - Preventive Maintenance Investment

The actual amount spent on Preventive Maintenance compared to the total amount spent on maintenance for the current year and the previous year. The data can be filtered further by Plant. Other filtering options, including Department, Area and Asset, are available in the Chart Field List.

S_CHT147 - Preventive Work Orders

The number of Preventive Work Orders compared to Total Work Orders, for the current year and the previous year. The data can be filtered further by Plant. Other filtering options available in the Chart Field List include: Department, Area and Asset.

Metrics

S_MTRC5 - Percent Preventive Work - sdbp_metric_pct_pm_wos

This metric is to describe the relationship between the number of PM Work Orders and the total number of Work Orders as a percentage. A PM Work Order is a Work Order with work type "P". It provides a means to monitor and improve the ratio of the number of PM Work Orders versus the total number of Work Orders.

S_MTRC10 - Percent PM Investment - sdbp_metric_pct_pm_investment

Describes the relationship between the PM WO dollars and the total dollars of all WOs as a percentage. PM Work Orders provide a means to monitor the dollar amount being invested in preventive maintenance versus the total dollar amount used for maintenance.

S_MTRC8 - Late PMs for Safety Equipment - sdbp_metric_late_pms_safety

A count of the total number of PMs that are late and related to Safety Critical Equipment. It provides a means to monitor and improve on the number of Safety Equipment related PMs that are late.

S_MTRC9 - Late PMs - sdbp_metric_late_pm

This metric is a count of the total number of PMs that are late. It provides a means to monitor and improve on the number of PMs that are late.

PM Event Module

Code Tables

Code Table 108: Event Groups

Event Group field - Define valid values to categorize PM Masters into logical groups. For example, all PMs that should cycle in the Winter may be in the group 'Winter' or all PMs involved in a major shutdown would be in the group 'Major.' The Event Groups field only appears on Event Type PM Masters (defined in the Schedule Basis field).

Code Table 109: Event Types

Event Type field - Further define Events by type. For example, PMs that should cycle in the Winter that are related to snow removal could be called "Removal". The Event Types field only appears on Event Type PM Masters (defined in the Schedule Basis field).

Copy Record

PMEVENT - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

FMEA Template Module

Fields

Sequence No.: FMEA Template ID

The FMEA Template ID is comprised of a unique ID (Ex. “11000000000018”). FMEA Template IDs can be set to be system-generated or created manually.

TABLE NAME - SA_FMEA_TEMPLATE - The database table that the sequence number is generated for.

Business Rules

FMEA Template RPN Defaults Rule

Failure Type	Severity	Occurrence	Detection
EO	5	4	2
ES	9	5	3
HE	2	6	8
HO	6	7	9
HS	10	8	10

Define default values to be used for fields when a new FMEA Template record is created. Enter values as appropriate to your business practices. The lists of values for the codes are defined by the corresponding code tables.

Failure Type, Severity, Occurrence, and Detection

For each failure type, enter the Severity, Occurrence and Detection. These values are multiplied together to derive the Risk Priority Number (RPN). The RPN gauges the severity of failure modes, with 1000 being the worst and 1 being the least.

EE - Evident economic failure which will have an adverse economic impact on operations.

EO - Evident operational failure which will have an adverse impact on operations.

ES - Evident safety failure which will have an adverse impact on safety and represents a potential danger to life and property.

HE - Hidden economic failure which will have an adverse economic impact on operations.

HO - Hidden operations failure which will have an adverse impact on operations.

HS - Hidden safety failure which will have an adverse impact on safety and represents a potential danger to life and property.

Code Tables

Code Table 9: Repair Codes (Length = 10)

Repair Code field - Define types of repair that may be done. Possible repair codes may include rebuild, replace, require, etc.

Code Table 10: Failure Codes (Length = 10)

Failure Code field - Define types of equipment failure that may occur. Typical failure codes may include corrosion, distortion, erosion, etc.

Code Table 51: Failure Modes (Length = 10)

Failure Mode field - Define further codes to identify failures found while work was being performed. Failure mode is defined as “any event which is likely to cause an asset (or system or process) to fail.” Some examples would be: deterioration, lubrication failure, dirt or contamination, disassembly, capability reducing' human error, deliberate overloading, unintentional overloading, incorrect process material, initial incapability, etc.

Code Table 52: Root Cause Codes (Length = 10)

Root Failure Cause field - Define codes to further identify the base cause which created the failure. Some examples include: Stresses, degradation of insulation, lack of lubrication, breakdown of lubrication, blocking, sticking, jamming, weld failure, solder failure, fatigue, corrosion, vibration, Anthropometric=cannot reach, human sensory=cannot see/smell/hear, physiological= hot/cold/loud/working too long and psychological=slip/lapse or mistake/violation. (ex: control valve left shut due to inability to get into tight space), operator error, under-designed, operator error combined with under-designed, out of specification, desired performance is outside of assets capability, etc.

Code Table 189: Work Action Codes (Length = 8)

Further Action field - Define codes for further action required. Examples include adjust, align, etc.

Code Table 344: FMEA System Code

FMEA System field - Define codes for FMEA systems that assets belong to.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Create FMEA Failure Item

Grants a user the ability to create FMEA template failure line items.

Create FMEA PM Control

Grants a user the ability to create FMEA PM Control by selecting the Create PM Control action on an FMEA record.

Asset PM Control

You can use the Asset PM Control module to create and manage identical PM Masters for all assets in a specified Class. This is useful when your operations require the same maintenance to be performed on a group of similar assets. By using the Asset PM Control module, you save the effort of having to update each Asset record independently with the same PM Master information.

An Asset PM Control record includes the scheduling parameters that are common to all assets in the specified Class. The record can also be set to apply only to certain Makes and Models within the specified class in the case of fleet assets (vehicles).

Fields

Sequence No.: Control No.

The Asset PM Control record number is comprised of a unique ID (Ex. "00011"). Asset PM Control record numbers are typically created by users.

TABLE NAME - SA_PM_FLEET_CONTROL - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Class

The list of values for the Class field is controlled by the Asset Class module.

Code Tables

Code Table 67: Vehicle Make (Length = 10)

Make field - Define codes to further describe vehicles by Make. Typical Vehicle Makes are Ford, Chevy, Toyota, etc. for Passenger Vehicle or Caterpillar for Industrial Vehicle. Vehicle Make is one of the search criteria on the Fleet Asset Search Options screen.

Vehicle Model Code Tables

Model field - Define codes to further describe vehicles by Model. There are a series of user setup code tables that are linked to Code Table 67 for Vehicle Make. As an example, if the vehicle (Fleet Asset) is a Ford F-150 Pickup truck, Code Table 67 would contain Ford, with a link to another Code Table (ex: 3000) where Code Table 3000 contains all the Make codes for Ford vehicles. In this example, Code Table 3000 would contain at least "F-150" as a value. The Vehicle Model code is only searchable from the Fleet Asset Search Options screen if the Vehicle Make has already been selected and the Vehicle Make selected has a Model listed in the code table that it's linked to.

Code Table 344: FMEA System Code

FMEA System field - Define codes for FMEA systems that assets belong to.

Business Rules

PM Control Types Rule

PM Control Type	Benchmark No.	Asset/Fleet
APMC1	B000593	ASSET
ASSET1	B000485	ASSET
BYB1	B000047	FLEET
BYB2	B000129	FLEET
BYB_MAX_FLEET_PM_TYPE23456	B000047	FLEET
CAK1	B000006	FLEET
CD1-01	B000585	FLEET
ILB ENGINE OVERHAUL	B000472	FLEET
ILBV1 OILCHANGE	B000032	FLEET
JEB	B000504	FLEET
MAV	B000130	FLEET
QBP_1	B000122	FLEET
QBP_2	B000123	FLEET

This rule defines Fleet and Asset control types and the corresponding Benchmark Work Order for each type. The rule helps to distinguish between fleet and asset control types.

PM Control Type

Note: The following items are EXAMPLES of possible PM Control Types configuration.

A - This letter denotes a basic 4,000 mile PM that is performed in accordance with an “A” checklist. This PM should be based on mileage or a calendar-interval basis.

B - This letter is used to indicate a more extensive list of items to check. This PM should be based on mileage or a calendar interval basis.

C - This letter denotes the most comprehensive checklist of items to be performed. This PM should be based on mileage or a calendar-interval basis.

G - This letter indicates a transmission service type of maintenance activity. This PM should be used on a calendar-interval basis.

H - This letter indicates that the engine coolant should be changed. This PM should be based on a calendar-interval basis.

Benchmark No.

Enter the Benchmark Work Order Number that corresponds to the PM Control Type. Batch processing uses the entered Benchmark Number associated with a PM Control Type to create a work order when an Asset PM Master is cycled.

Asset/Fleet

Enter whether this control type corresponds to an Asset or to a Fleet.

Copy Record

FLEETPMC - COPY RECORD


Add this to users’ responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.



PM Route Module

Business Rules

PM Route Options Rule



Name	Option	Value
ALLOCATE COSTS TO ASSETS	ON	APPROVED

Control parameters used in PM Route processing.

Name, Option, and Value

ALLOCATE COSTS TO ASSETS - If you set the Allocate Costs to Assets rule key to ON, the system will manage the costs for a work order task on a PM Route so that the costs are evenly distributed among the assets on the route. The system completes this re-distribution of costs by creating cost adjustment records.

The value is the status that the adjustment records will be created in.

Code Tables

Code Table 20: PM Route Types

Type field - Define PM Route types. Typical entries include Adjust, Calibrate, Clean, Exercise, Inspect, Lubricate, Reading, Sample and Test.

Code Table 49: PM Route Task Types (Route Stops View)

Task Type field - Define categories for tasks. Typical entries include Calib for instrument calibration, Vibration for vibration readings, Lube for a lubrication, etc.

Code Table 44: Lube Types (Route Stops View)

Type field (next to Sample Required?) - Define codes to identify the type of lubrication being used for the work. Typical Lube Types include Gear Oil, Engine Oil, Grease, etc.

Code Table 42: Lube Methods (Route Stops View)

Method field - Define codes to identify the method for lubrication. Examples include Gun, Tube, etc.

Batch Processes

Cost Adjustment for PM Route - `sdbp_cost_route.cost_route`;

Generates and posts cost adjustments to remove charges from the work order task account and distribute them among the PM Route's assets. Labor and material costs related to accomplishing the Scheduled PM Route are charged against the work order's task and then distributed amongst the assets that were finished on the PM Route.

PM Routing - sdbp_pm_routing;

Updates PM Stops based upon the Completed Dates entered on a Scheduled PM Route List. Next Schedule Dates are then adjusted as required and the PM Route Stop item is set to Posted.

Copy Record

PMROUTE - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Reports

S_RPT058 - PM Route Report

Lists PM Route information.

Project/Subproject Module

Fields

Sequence No.: Project ID

The record number is comprised of a unique ID (Ex. "00000000001"). Project record numbers are typically set to be system generated.

TABLE NAME - SA_PROJECT - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Approval Route Field

Designate approvers for Direct Charges in the Approval Limits module of the Administration subsystem under Approvals and Routes.

Code Tables

Code Table 310: Supervisor Title

Supervisor field - Define the supervisor titles to be used for various records. These codes define a supervisory position, not a specific person. Some examples of titles are Head Supervisor, Maintenance Supervisor, and Foreman.

Copy Record

PROJECT - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Business Rules

Account Creation from Projects Rule

The screenshot shows a configuration window titled "Business Rule ACCOUNT CREATION FROM PROJECTS". It contains the following fields and sections:

- Rule ID:** ACCOUNT CREATION FROM PROJECTS
- Business:** Business
- Parameter:** Parameter
- Limit?:**
- Desc:** This rule allows automatic creation of an Account Number via the Project module.
- Comment:** ALLOW AUTO CREATE is a function which controls whether or not an Account Number is automatically created via the Project module. When a Project is created in the Maintenance subsystem, a Project ID is
- Table:** A table with two columns: "Account Creation" and "Option Status".

Account Creation	Option Status
ALLOW AUTO CREATE	ON
- Description:** ON: An Account Number can be created from within the Project Module. asdf

Allow or Disallow automatic creation of an Account Number via the Project module.

Note: The LOV on the account # will display only valid account #'s, and will substitute the actual Project ID for PROJE .

Account Creation and Option Status

ALLOW AUTO CREATE - controls whether or not an Account Number is automatically created via the Project module. When a Project is created in the Maintenance subsystem, a Project ID is assigned. For each Subproject generated, the user has the opportunity to create an Account Number specifically for that Subproject by listing an Account Number that contains the character string PROJE .

Once the Project/Subproject is approved, the system generates an Account Number in the Account module by replacing the PROJE with the displayed Project ID. Accounts generated in this manner are set to INACTIVE status so that they would not be readily available for use elsewhere in the system.

Project Budget Options Rule

Business Rule PROJECT BUDGET OPTIONS

Rule ID: PROJECT BUDGET OPTIONS Business List Limit?

Desc: Options for Project Budget Display and Processing

Comment:

Option	Status	Value
ALERT DOLLAR TOLERANCE	OFF	5000
ALERT PERCENT TOLERANCE	OFF	10
ALLOW BUDGET UPDATE	ON	
CHECK APPROVAL DOCUMENT	ON	
CHECK PROJECT LIMIT	OFF	
PROJECT BUDGET OPTIONS	ON	

Description:
Batch Processing will send an Alert when the costs approach the budget amount less than this dollar tolerance and the status of this option is ON.

Set options for Project Budget Display and Processing.

Option, Status, and Value

ALERT DOLLAR TOLERANCE - If this option is set to ON the system will send an Alert when Project costs approach the budget amount less than the dollar tolerance entered in the Value field. Referring to the Batch Job Control Business Rule, SDBP_PROJECT_ALERT uses the Project Budget Options Business Rule for determining if a percent and/or dollar tolerance is to be used. The estimated and committed Subprojects costs are compared to the budget amount minus the tolerance. An alert is sent to the Subproject supervisor_name and to the Project project_manager when these costs are above the target amount.

ALERT PERCENT TOLERANCE - If this option is set to ON the system will send an Alert when the costs approach the budget amount less the percent tolerance entered in the Value field or the budget amount. Referring to the Batch Job Control Business Rule, SDBP_PROJECT_ALERT uses the Project Budget Options Business Rule for determining if a percent and/or dollar tolerance is to be used. The estimated and committed Subprojects costs are compared to the budget amount minus the tolerance. An alert is sent to the Subproject supervisor_name and to the Project project_manager when these costs are above the target amount.

ALLOW BUDGET UPDATE - If this option is set to ON, Subproject Budgets can be updated when the Project/Subproject is in Approved status.

CHECK APPROVAL DOCUMENT - This option controls how the system processes approvals for subprojects and for work orders that reference a subproject. Set this rule key to ON if the work order related to the subproject does not require approval after the subproject is approved. Set this to OFF if approval checking for the subproject should be disabled but the resulting work order must go through standard approval processing.

ON - A dollar limit approval authority is required to approve the subproject, but once the subproject is approved the related work order does not require approval checking. With this setting a user without work order approval authority can change the work order status to Approved or Active as long as the subproject has been approved.

Even with this option set to ON the user changing the Work Order status to Approved must still have the responsibility functions WO TO ACTIVE, WO TASK TO ACTIVE

and ACTIVATE WO MATERIAL in order to be able to create a Work Order Task where charges can be applied. So there are still checks in place to only allow users with authority to create Work Order Tasks where charges can be applied.

OFF - There is no approval checking on subproject records. Any work order referencing the project/subproject must go through standard processing to obtain approval. With this setting there is no Pending Approval status on Subproject records.

Eliminating Pending Approval status on the project forces planners and approvers to communicate directly regarding the subproject rather than relying on system alerts. This ensures that work orders and subprojects will not be approved haphazardly, yet your organization can benefit from simplified processing.

CHECK PROJECT LIMIT - If this rule key is set to ON the system will verify that the budget amount totals for the Project do not exceed the Project limit when the Subprojects are approved.

PROJECT BUDGET OPTIONS - This rule key controls where the approval of the Project occurs. When set to ON, the approval is at the Subproject level and each subsequent Subproject will be automatically be in CREATED status. When this rule key is set to OFF, the approval is at the Project header level and each Subproject will be created set to APPROVED status when the overall Project is approved.

Project Management Rule

Business Rule PROJECT MANAGEMENT

Rule ID: PROJECT MANAGEMENT Business List Limit?

Desc: This business rule helps in establishing connection between Oracle Database and MS Project application through Domain Service Name and helps you to open MS Project File on a specified directory.

Comment:

Key	Option	Value
DSN		SERIES
MS_PROJECT_EXE		C:\Prog
UPDATE MSP TASK DATES	OFF	

Description:

Business Rule PROJECT MANAGEMENT

Rule ID: PROJECT MANAGEMENT Business List Limit?

Desc: This business rule helps in establishing connection between Oracle Database and MS Project application through Domain Service Name and helps you to open MS Project File on a specified directory.

Comment:

Key	Option	Value
DSN		SE
MICROSOFT PROJECT VERSION	MSP2000	SE
MS_PROJECT_EXE		
ODBC DATASOURCE NAME		

Description:

Establish a connection between Oracle Database and MS Project application through Domain Service Name. You can also set the system to open MS Project Files on a specified directory.

Key, Option, and Value

DSN - Domain Service Name.

MS_PROJECT_EXE - Launches MS Project.

UPDATE MSP TASK DATES - If this rule key is set to OFF the system will not update MS Project tables when task records are updated.

Project Work Order Account Rule

Business Rule PROJECT WORK ORDER ACCOUNT

Rule ID: PROJECT WORK ORDER ACCOUNT Business List Limit?

Desc: This business rule controls the connection between project/subproject and the account number on a work order/task.

Comment: The Acct Update determines if the account number on the work order and task can be updated when a project/subproject is entered. The Acct Cascade determines if the project account no is to be copied to all

Project Type	Acct Update	Acct Cascade
CAPITAL	NO	YES
DEMOLITION	YES	YES
MAINTENANCE	YES	NO
RESTORATION	YES	YES
SHUTDOWN	NO	NO

Description: Capital Project

Controls the connection between Project/Subproject and the account number on a work order/task.

Project Type

The values entered in this column will be used to build the list of values in the Type field on Subproject records. Some examples of types of projects are: Capital, Maintenance, or Shutdown. Once project types are created, define distinct settings for each type of project by setting values in the Account Update and Account Cascade fields.

If the Account Update key value is set to YES and Account Cascade is also set to YES then when a new Task is added to a Work Order and the Asset ID is changed (or defaulted from the previous Task) the account number will be copied from the Asset ID along with the Department and Area.

Acct Update

The Acct Update determines if the account number on the work order and task can be updated. The system automatically overrides the asset account number with the Subproject account number when you fill in the Subproject ID. If set to Yes, this rule key allows you to override that functionality and change the account number back to the asset account number.

Acct Cascade

The Acct Cascade determines if the Project Account No. is to be copied to all of the work order tasks when the work order is activated.

Work Order Processing Rule

Business Rule WORK ORDER PROCESSING

Rule ID: WORK ORDER PROCESSING Business Parameter Limit?

Desc: This rule controls specific Work Order processes as specified in the "WO Processing Rule" column.

Comment: DIRECT PURCHASE determines a Requisition is to be created for direct purchase items estimated on a Work Order Task. When the Task is activated, listed direct purchase items are processed, creating a Requisition. You can determine the status of the Requisition by setting the Requisition status in the Value column.

WO Processing Rule	Document	Status	Value
ALLOCATE COSTS TO ASSETS		OFF	APPROVED
APPLY CHANGE REQ CREATED FR WO		ON	
AUTO ADD DEPENDENT MATERIALS		ON	
AUTO CLOSE CHECKOUT REQUESTS		ON	
AUTO UPDATE TRAVEL TRIPS		ON	
BUYER CODE	REQUISITION		GST
CHANGE REQUEST ENFORCEMENT		ON	
CHECK OPEN MATERIAL RECORDS		ON	
COPY EMERGENCY WO TO SCHEDULE	DAILY	ON	NEXT
DELAY CONSTRUCTION ASSET VALUE		ON	
DIRECT PURCHASE	REQUISITION	PENDING APPROVAL	
DIRECT PURCHASE BLANKET		ON	
DIRECT PURCHASE DUTY TAX			0

Description: Set this rule key to ON to have the system reverse asset costs on work order tasks and distribute the costs across assets on the asset list by creating adjustment records. The status of the resulting Cost Adjustment record will be the status entered in the Value column. Check OFF THIS if you do not want to include the labor markup values.

Determine whether or not labor markup information is included in the Cost Summary view.

WO Processing Rule, Document, Status and Value

LABOR MARKUP ON COST SUMMARY - This key determines if labor markup transactions are included in the Cost Summary views in the Work Order and Project / Subproject modules. Set the value to ON to include the M1, M2 and M3 Labor Markup Transaction Codes in the Cost Summary views. Set the value to OFF if you do not want to include the labor markup values. The default setting is OFF.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Allow WO Project Update

Allows users to update the Project / Subproject on Active Work Orders as long as there are no "Actual" costs for that Work Order.

Project Closed to Finished

Grants the ability to change the status of a Project from CLOSED to FINISHED.

Project Finished to Closed

Grants the ability to change the status of a Project from FINISHED to CLOSED.

Project Management

Grants access to the Project Management view in the in the Project/Subproject module.

Subproject Approved to Created

Grants the ability to change the status of a Subproject from APPROVED to CREATED.

Subproject Finished to Approved

Grants the ability to change the status of a Subproject from FINISHED to APPROVED.

Batch Processes

Project Alert - `sdbp_project_alert`;

Uses the Project Budget Options Business Rule for determining if a percent and/or dollar tolerance is to be used. The estimated and committed subprojects costs are compared to the budget amount minus the tolerance. An alert is sent to the subproject supervisor_name and to the project project_manager when these costs are above the target amount.

Charts

S_CHT149 - Project Analysis

The Budget Amount, Original Estimate, Revised Estimate, Committed Costs, and Actual Amount for Projects. The data can be filtered by Plant and Project Status.

Views

Subproject

The screenshot shows a web-based form titled "Project 000000006 Subproject". The form contains the following fields and values:

- Subproject ID: 1
- Status: Approved
- Date: 15 DEC 2000 13:18:08
- Type: CAPITAL
- Create Account: N
- Account No.: RVM1-N-ASSET-COMP-STORES PO-001
- Desc.: test
- Supervisor: RVEKSLER
- Subproject Budget: 10,000.00
- Next Approver: (empty)
- Estimated: 15 DEC 2000
- Actual: 27 DEC 2000

Microsoft Project Interface

The Microsoft Project Interface is not certified for use in the Web environment. The Project/Subproject module includes a View that provides an interface between the Oracle Utilities Work and Asset Management system and the Microsoft Windows based application, MS Project. You can use wizards on the Actions list in the Project/Subproject module to export Project information to MS Project and to launch MS Project. Users should be aware that changes made in MS Project can not be exported back into the system. Any tasks that are created or deleted in MS Project as well as dates that are changed will not be reflected in the system. Any modifications that need to be made to the project should be made in the system then exported to MSProject. The system should be configured in the Project Management business rule and the Default File Locations business rule. to ensure that this interface works properly.

Project Management Configuration

Before the Project Management interface can be used, Microsoft Project must be installed on each user computer, and the Default File Locations business rule must be configured with the location of the MS Project program file.

A typical path is entered during the installation process, but your DBA or System Administrator should verify that it is correct and change it if necessary.

The system is certified for MS Project 2003 and 2007.

Configuring in User Profile

If not all users have Microsoft Project installed in the same directory, individual users can override the path specified in the business rule by inserting an alternate path in their User

Profile. To do this, open the User Profile and insert a new key name, selecting 'Default MS Project Path' from the drop-down list. Then enter the complete path (including the name of the executable file) as Key Value 4, and save the record.

Report Output

While it is not necessary to configure, it is useful to note that the Report Output Physical Directory rule key in the Web Configuration Business rule indicates the physical location where the output of the generated xml file is temporarily stored when data is transferred from the Project/Subproject module to the MS Project application.

Runtime Entry Module

Meter readings can be entered in the Runtime Entry, Task Closeout, PM Master, Consumables modules or through an external interface. Information collected here is automatically used to update PM Master run-time based records (for the listed asset and run-time type).

Code Tables

Code Table 107: Meter Units

Meter Units column - Define valid names for the types of measurement units that can be metered and tracked to determine asset operation.

Business Rules

Asset Runtime Rule

Period/Month	Status
END OF MONTH	ON

Define how the Asset Runtime per month or per period will be calculated. The rule is used in conjunction with the stored database procedure SDBP_RUNTIME.

Period/Month and Status

ALLOW LOWER RUNTIME - This key only affects assets with depreciation method of Units of Production. A Status of YES allows entry of a reading lower than or equal to the last reading. A Status of NO only allows entry of a reading higher than the last reading.

END OF MONTH - Entering ON or OFF in the status determines the period of time the SDBP_RUNTIME calculates the Asset Runtime from. ON calculates from the end of one month or period to the end of the next month or period. OFF calculates from the beginning of one month or period to the beginning of the next month or period.

Daily Schedule Module

Business Rules

Auto Generate Daily Schedule Rule

The screenshot shows a configuration window titled "Business Rule AUTO GENERATE DAILY SCHEDULE". It contains the following fields and controls:

- Rule ID:** A text field containing "AUTO GENERATE DAILY SCHEDULE".
- Business:** A dropdown menu with "Business" selected.
- List:** A dropdown menu with "List" selected.
- Limit?:** A checkbox that is currently unchecked.
- Desc:** A text area containing "This rule allows automatic cycling of unfinished Work Order Task(s) to the Crew's next day's schedule."
- Comment:** A text area containing "All Crews may be entered. Enter ON in the 'Generate?' column to have unfinished Work Order Task(s) cycle to Crew's next day's schedule. Enter OFF in the 'Generate?' column to have unfinished Work Order".
- Crew:** A list box containing "BYB", "PM2", "RAY", "RVM", and "RVM_1".
- Generate?:** A column of five text boxes, each containing "ON", corresponding to the crew names in the list box.
- Description:** An empty text area at the bottom of the window.

Control automatic cycling of unfinished work order tasks to the crew's next day's schedule.

When the `sdbp_reschedule.job_reschedule` batch job is run, work order tasks that are in ACTIVE status are placed on the next day's schedule for that task's crew. Schedules are generated according to the days and hours entered in the Crew Daily Hours view of the Crew module.

Note: The Automatic Scheduling feature only applies to ACTIVE work order tasks. If you are using the Scheduling modules to schedule PLANNED (or non-active) work order tasks, you must manually move the work tasks to future schedules. This is due to the fact that the "completion" of a PLANNED work order task does not result in the work order task being FINISHED or CANCELED. The Automatic Scheduling option would continue to rollover the work order task to the Planners schedule until work was actually finished.

Crew / Generate

Enter any valid crew that exists in the Crew module then enter ON or OFF in the Generate column to determine whether or not the system should cycle unfinished work order tasks to the crew's next day's schedule. Any crew that is not listed will be defaulted to OFF and no schedules will be created automatically for that crew. Schedules are generated according to the days and hours entered in the Crew Daily Hours view of the Crew module.

Default Backlog Groups Rule

Business Rule DEFAULT BACKLOG GROUPS

Rule ID: Business Limit?

Desc: This rule allows a user to build a relationship between a crew and a backlog group.

Comment: The following modules are affected by this Business Rule:
Work Request, Work Order, Work Order Task, Benchmark Work Order and PM Master (detail - Additional

Crew	Backlog Group
BYB	BYBBLG
CAK1	CAKBLG
DP1	DEPOT1
GE	CAKBLG
LAB	BYBBLG
MASON	DEPOT1
RJB	RJBBLG
RVM	RVMBLG

Description:

Build a relationship between crews and backlog groups (sometimes called backlog crews) for Work Requests, Work Order Tasks, Benchmark Work Order Tasks, PM Masters, and on Schedules.

An example of how the concept of a backlog crew may be used is that Crew A (Crew) works 1st shift and Crew B (Backlog Group) works 2nd or 3rd shift and takes on any unfinished tasks originally scheduled for Crew A (Crew) on 1st shift.

Crew and Backlog Group

Enter the crews and the associated Backlog Groups for each in the appropriate columns.

Work Week Rule

Business Rule WORK WEEK

Rule ID: Business Limit?

Desc: This rule defines the work week.

Comment: This rule will be used to determine which Daily Schedules could be grouped together into a Weekly Schedule.

Crew	Week Start	Week End	Period
ABC	TUESDAY	SATURDAY	
RAY	MONDAY	FRIDAY	
RVM	MONDAY	FRIDAY	
RVM_01	TUESDAY	SATURDAY	

Description:

Define the workweek.

This rule is used to define the days of the week that a crew is available to be scheduled in a work week.

Crew

Enter into the CREW column the crew name.

Week Start and Week End

The WEEK START and WEEK END columns dictate the start of the workweek and the end of the work week for each crew listed in the CREW column.

Period

This column will be available in a future release.

Scheduling Options Rule

Option	Status
COPY INTERRUPTION CODE	OFF

This rule defines options used in Daily and Workweek Scheduling.

Copy Interruption Code

This rule determines whether the system will copy the interruption code when copying or merging a WO Task from one scheduling record to another. When set to ON, the system will copy the interruption codes. When set to OFF, the system will not copy the interruption codes.

Code Tables

Code Table 1190: Daily Schedule Types

Type field - Use this code to define the types of schedules that can be created. Typically these types describe the work to be done, however codes can be set to describe any schedule type.

Code Table 2501: Interruption Codes

Interruption Code field - Interruption codes are mainly used for compliance tracking to identify what occurred to impact the planned schedule.

Batch Processes

Reschedule - sdbp_reschedule.job_reschedule;

Reviews all active work order tasks which are unfinished and places them on the Daily and / or Weekly Schedules as defined in the Auto Generate Daily Schedule and Auto Generate Weekly Schedule Rules. Work Order which were just generated by PM Master processing will also be placed on the Daily / Weekly Schedule.

PM Cycle - sdbp_pm_cycle.job.start_job;

Reviews active PM Masters and cycles those that are due, creating work orders in the status defined in the PM Master Parameters Business Rule. If the PM is being cycled and the Benchmark's component is no longer installed on the Benchmark's asset, the system generates a work order with the asset from the Benchmark and will not bring over the component.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Activate Checkout Request from Schedule

Users with this responsibility will have available a column of check boxes in the Checkout Request view of the Daily Schedule module as well as an action which allows users to activate the checkout requests from the scheduling record.

Merge Task WOWeek to Day Schd

Grants access to the Merge All Tasks to Daily Schedule and Merge Selected Tasks to Daily Schedule. The actions allow users to copy or move the tasks to specified Daily Schedule records.

Reports

S_RPT152 - Daily Schedule Assignments Report

Lists employees and the work orders that are assigned to them on the selected day.

S_RPT041 - Daily Schedule Report

Lists the work order tasks scheduled for a selected day.

Installation Parameters

SCHEDULING TOTAL EST HRS DISP

ON/OFF

If set to ON, will display Total Hours Scheduled and Labor Estimate for each craft within the Daily and Workweek Scheduling modules.

Workweek Schedule Module

Business Rules

Auto Generate Weekly Schedule Rule

The screenshot shows a configuration window titled "Business Rule AUTO GENERATE WEEKLY SCHEDULE". It contains the following fields and controls:

- Rule ID:** AUTO GENERATE WEEKLY SCHEDULE
- Business:** Business
- List:** List
- Limit?:**
- Desc:** This rule allows automatic cycling of unfinished Work Order Task(s) to the Crew's next week's schedule.
- Comment:** All Crews may be entered. Enter ON in the "Generate?" column to have unfinished Work Order Task(s) cycle to Crew's next week's schedule. Enter OFF in the "Generate?" column to have unfinished Work
- Crew:** A list box containing BYB, RVM, and RVM_1.
- Generate?:** A list box containing ON, ON, ON, and empty cells.
- Description:** An empty text area.

The Auto Generate Weekly Schedule Rule allows automatic cycling of unfinished Work Order Task(s) to the Crew's next week's schedule.

When the sdbp_reschedule.job_reschedule batch job is run, work order tasks that are in ACTIVE status are placed on the next week's schedule for that task's crew. Schedules are generated according to the days and hours entered in the Work Week business rule.

Note: The Automatic Scheduling feature only applies to ACTIVE work order tasks. If you are using the Scheduling modules to schedule PLANNED (or non-active) work order tasks, you must manually move the work tasks to future schedules. This is due to the fact that the "completion" of a PLANNED work order task does not result in the work order task being FINISHED or CANCELED. The Automatic Scheduling option would continue to rollover the work order task to the Planners schedule until work was actually finished.

Crew / Generate

Enter any valid crew that exists in the Crew module then enter ON or OFF in the Generate column to determine whether or not the system should cycle unfinished work order tasks to the crew's next week's schedule.

Any crew that is not listed will be defaulted to OFF and no schedules will be created automatically for that crew. Schedules are generated according to the values entered in the Work Week business rule.

Default Backlog Groups Rule

Business Rule DEFAULT BACKLOG GROUPS

Rule ID: Business Limit?

Desc: This rule allows a user to build a relationship between a crew and a backlog group.

Comment: The following modules are affected by this Business Rule:
Work Request, Work Order, Work Order Task, Benchmark Work Order and PM Master (detail - Additional)

Crew	Backlog Group
BYB	BYBBLG
CAK1	CAKBLG
DP1	DEPOT1
GE	CAKBLG
LAB	BYBBLG
MASON	DEPOT1
RJB	RJBBLG
RVM	RVMBLG

Description:

The Default Backlog Group business rule allows a user to build a relationship between a crew and a backlog group for Work Requests, Work Order Tasks, Benchmark Work Order Tasks, PM Masters, and schedules.

An example of how the concept of a backlog crew may be used is that Crew A (Crew) works 1st shift and Crew B (Backlog Group) works 2nd or 3rd shift and takes on any unfinished tasks originally scheduled for Crew A (Crew) on 1st shift.

Crew and Backlog Group

Enter valid Crew codes (Code Table 15) in the Crew column. In the Backlog Group column enter Backlog Group codes (Code Table 110) associated with the Crew.

Work Week Rule

Define the workweek.

Business Rule WORK WEEK

Rule ID: Business Limit?

Desc: This rule defines the work week.

Comment: This rule will be used to determine which Daily Schedules could be grouped together into a Weekly Schedule.

Crew	Week Start	Week End	Period
ABC	TUESDAY	SATURDAY	
RAY	MONDAY	FRIDAY	
RVM	MONDAY	FRIDAY	
RVM_01	TUESDAY	SATURDAY	

Description:

This rule is used to define the days of the week that a crew is available to be scheduled in a work week.

Crew

Enter into the CREW column the crew name.

Week Start and Week End

The WEEK START and WEEK END columns dictate the start of the workweek and the end of the work week for each crew listed in the CREW column.

Period

This column will be available in a future release.

Code Tables

Code Table 2500: Daily Schedule Types

Type field - Define the types of schedules that can be created. Typically these types describe the work to be done, however codes can be set to describe any schedule type.

Code Table 2501: Interruption Codes

Interruption Code field - Interruption codes are mainly used for compliance tracking to identify what occurred to impact the planned schedule.

Batch Processes

Reschedule - sdbp_reschedule.job_reschedule;

Reviews all active work order tasks which are unfinished and places them on the Daily and / or Weekly Schedules as defined in the Auto Generate Daily Schedule and Auto Generate Weekly Schedule Rules. Work Order which were just generated by PM Master processing will also be placed on the Daily / Weekly Schedule.

PM Cycle - sdbp_pm_cycle.job.start_job;

Reviews active PM Masters and cycles those that are due to create work orders. The new work order status is defined in the PM Master Parameters Business Rule. If the PM is being cycled and the Benchmark's component is no longer installed on the Benchmark's asset, the system generates a work order with the asset from the Benchmark and will not bring over the component.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Merge Task WOWeek to Day Schd

Grants access to the Merge All Tasks to Daily Schedule and Merge Selected Tasks to Daily Schedule. The actions allow users to copy or move the tasks to specified Daily Schedule records.

Installation Parameters

SCHEDULING TOTAL EST HRS DISP

ON/OFF

If set to ON, will display Total Hours Scheduled and Labor Estimate for each craft within the Daily and Workweek Scheduling modules.

Schedule Plan Module

Business Rules

Work Week Rule

The screenshot shows a configuration window titled "Business Rule WORK WEEK". It contains the following fields and sections:

- Rule ID:** WORK WEEK
- Business:** Business
- List:** List
- Limit?:**
- Desc:** This rule defines the work week.
- Comment:** This rule will be used to determine which Daily Schedules could be grouped together into a Weekly Schedule.
- Crew:** A list box containing ABC, RAY, RVM, and RVM_01.
- Week Start:** A table with rows for TUESDAY, MONDAY, MONDAY, and TUESDAY.
- Week End:** A table with rows for SATURDAY, FRIDAY, FRIDAY, and SATURDAY.
- Period:** An empty table with four rows.
- Description:** An empty text area.

The Work Week Rule defines the days of the week that a crew is available to be scheduled in a work week. This determines which Daily Schedules can be grouped together into a Workweek Schedule.

Crew

Enter the crew name in the Crew column.

Week Start and Week End

The WEEK START and WEEK END columns dictate the start of the work week and the end of the work week for each crew listed in the CREW column.

Period

This column will be available in a future release.

Reports

S_RPT153 - Schedule Plan Report

Provides a listing of the crew plans in a schedule plan along with the associated daily plans and work order tasks. The report also shows the hours and crafts assigned for each task.

Direct Charges Module

Fields

Sequence No.: Direct Charges No.

The record number is comprised of a unique ID (Ex. "010000066"). Direct Charge record numbers are typically set to be system generated.

TABLE NAME - SA_DIRECT_CHARGES- The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Approval Route Field

Designate approvers for Direct Charges in the Approval Limits module of the Administration subsystem under Approvals and Routes.

Owner Field

The Credit Card Info View of User Profile module is used to populate the list of values for the Owner field in the Direct Charges module.

Note: You must be logged in as the user to insert, view or update credit card information for each user. This data can also be entered through data migration.

Code Tables

Code Table 550: Direct Charge Category Codes

Category Field - Define categories for direct charges. Examples include Personal (to be used for reimbursement for business trips), Maintenance (to be used for Maintenance related Credit Card Purchases), Inventory (to be used for Inventory related Credit Card Purchases), Equipment (to be used for all equipment rentals) etc.

Business Rules

Direct Charge Types Rule

Business Rule DIRECT CHARGE TYPES

Rule ID: Business Limit?

Desc: This rule determines Direct Charge Types for Direct Charges.

Comment: Charge Types can be up to 10 characters. Status field allows you to enable/disable Direct Charge types. Units are from new Code Table 60. Standard Price field is the rate per unit. Expense code is the expense

Direct Charge Types	Status	Units	Std Price	Ex
COMPRESSOR	ALLOW	HOURS	35	OC
CRANE	ALLOW	DAY	1000	OC
CRANE HR	ALLOW	HOURS	50	OC
CREDIT	ALLOW	DAY	10	OC
KILOMETER	ALLOW	KILOMETERS	26	OC
LODGING	ALLOW	DAY	100	OC
MEALS	ALLOW	DAYS	50	OC
MILEAGE	ALLOW	MILES	34	OC
OPEN	ALLOW	NONE	15.5	OC
TOW HR	ALLOW	HOURS	10	OC
TRUCK	ALLOW	HOURS	12.50	OC
VEHICLE	ALLOW	DAYS	35	OC

Description: This is a really big compressor that blows lots of hot air!

Determines Direct Charge Types for Direct Charges.

Units are from new Code Table 60. Standard Price field is the rate per unit. Expense code is the expense code to charge (from EXPENSE CODE Business Rule).

Direct Charge Types

Enter the Charge Type codes into the DIRECT CHARGE TYPE column. Examples: Meals, Mileage, Rental. The Type Code can be up to 10 characters long.

Status

The STATUS column of each DIRECT CHARGE TYPE must be set to ALLOW or DISALLOW to enable or disable the use of each Type code.

Units

The Lists of Values for the Units fields reference Code Table 60 where Direct Charge Type Units are defined. Select the appropriate Unit code for each Direct Charge type.

Standard Price

Enter the STD PRICE rate for each type of Direct Charge.

Expense Code

Enter in the EXPENSE CODE column the specific expense code, if applicable, associated with this Direct Charge type. EXPENSE CODES are defined in the EXPENSE CODE Business Rule.

Processing

Default is set to STANDARD, but if the value is changed to OPEN, then that gives the users the ability to update the Standard Price and Amount fields on the Direct Charges Item.

Batch Processes

Direct Charges - sdbp_direct_charges.direct_charges;

Processes approved Direct Charges costs which have not yet been posted, and creates

new entries in the Direct Charges Log.

Cost and Closeout - smu_interface.sdbp_mu_interface (job_in, plant_in,'N');
Processes transactions entered in cost and closeout.

Copy Record

ODC - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Cost and Closeout

Adds the Cost and Closeout action to the user's home page action list.

Leave Request Module

Business Rules

Timekeeping Authority Rule

Username	Authority	Org Level	Override
63NEWUSER	SUPERVISOR		
FINE GRAIN CONTROL 1	SUPERVISOR		
FRED	SUPERUSER		
GUEST	SUPERVISOR		
JBROWN	SUPERVISOR	TITLE	
JCOOL	PAYROLL		

Use this rule to define which users can access and maintain timesheets, leave requests, and employee records. This rule only controls who has access to the records, approval authorization is controlled in the Approval Limits module.

Note: A supervisor defined in this module does NOT correspond to the Supervisor fields defined by code table 310.

Username

Enter individual Usernames to set an authority level for access to Employee records, Timesheets, and Leave Requests. Anyone not listed will have the DEFAULT authority. By setting the USERNAME column to DEFAULT and the AUTHORITY column to EMPLOYEE, all users will be granted employee level authority without your needing to identify them explicitly.

Authority

The Authority column defines the scope of a users' authority. The authority levels include: Employee, Supervisor, Superuser and Payroll.

EMPLOYEE - User can only view or modify their own timesheet or employee record. Org Level does not apply.

SUPERVISOR - User can view or modify their own records and records of members of the Org Level entered. The Org Level value is used to widen the scope of the Supervisor authority. Set the value to Department, Area, or Crew, and the system limits the corresponding username to have access to other user's records who share the same Department, Area or Crew on their EMPLOYEE record. If you enter TITLE as the Org Level, the username is limited to see the user's records who are on the same CREW module record with the username. This allows Supervisors to approve timesheets for multiple crews (any crew that they are on).

SUPERUSER - User can view or modify any record. Org Level does not apply.

PAYROLL - User can view or modify any record, as well as override or adjust Compensatory Time Accrual calculations. Org Level does not apply.

For example, If BIGBOSS is entered under username in this business rule with the

Authority set to Supervisor, and the Org Level set to Title, the system provides him access to the records for all users who are on the same CREW module records as BIGBOSS. If the Org Level is left blank or set to Crew the system provides BIGBOSS with access to the records of every user who has the same Crew entered on their EMPLOYEE module record as he has on his Employee record.

Org Level

The Org Level value is used to widen or narrow the scope of the Supervisor authority. See above for valid values and definitions.

Override

The override value is only used for those with the Supervisor or Superuser authority to temporarily promote them to Superuser or Payroll authority. Enter Superuser or Payroll in the Override column to give this authority to a user (to substitute for a supervisor who is on vacation, for instance). Filling in this value does not modify the authority of any other user. It can be changed or cleared later to restore the user to their original authority.

Timekeeping Leave Types Rule

Define which of the charge types set up in the Timekeeping Charge Types Rule are Leave Types.

This rule establishes a link between the leave types listed in Code Table 48 and the charge types listed in the Timekeeping Charge Types Rule.

Charge Type	Leave	Minimum Hrs.	Expense Code
C	COMP	1	00007
J	JURY	8	00008
S	SICK	8	00007
V	VACATION	8	00007

Charge Type

Items listed in the CHARGE TYPE column are directly linked to the Leave Types listed in Code Table 48, used in the Leave Summary and Scheduled Leave details under the Employee module, and the Timekeeping Charge Types Rule. For these Leave Types to be available, the STATUS column of the Timekeeping Charge Types Rule must be set to ALLOW.

Leave

This column is a description of the values listed in the CHARGE TYPE column

Minimum Hours

Enter in the MINIMUM HOURS column the number of hours an employee must work before beginning to accrue CHARGE TYPE hours.

Expense Code

Enter in the EXPENSE CODE column the specific expense code, if applicable, associated with this leave type.

Code Tables

Code Table 48: Leave Reason Codes

Reason column - Define leave reason codes. Codes might include Maternity, Sick, Vacation, etc.

Copy Record

LEAVEREQ - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Batch Processes

Leave Request - sdbp_post_leave;

Posts Leave Requests and creates timesheets for approved Leave Requests that have the Create Timesheet indicator checked and are in an open Pay Period.

Create New Leave Year sdbp_create_new_leave_year.new_leave_year;

Inserts leave records once per year for all employee records into the Employee Leave detail, carrying over remaining leave information from the previous year.

Reports

S_RPT065 - Employee Pay Period Time Report

Provides an Employee Timesheet for a specific pay period.

Payroll Voucher Module

The Payroll Voucher module is non-standard and is usually turned off.

Business Rules

Payroll Voucher Types Rule

Determines the account and expense code that payroll vouchers can be charged against.

The screenshot shows a configuration window titled "Business Rule PAYROLL VOUCHER TYPES". It contains the following fields and table:

- Rule ID:** PAYROLL VOUCHER TYPES
- Business:** Business
- List:** List
- Limit?:**
- Desc:** This rule determines what account and expense code payroll vouchers may be charged against.
- Comment:** The first column is the Voucher Charge Type; the second refers to the status of the charge type (ALLOW or DISALLOW); the third column is the expense code; the fourth column is the account number.
- Table:**

Voucher Type	Status	Exp Code	Ac
DENTAL	ALLOW	00008	G:
MEDICAL	ALLOW	00008	G:
UNIFORMS	ALLOW	00008	G:
VISION	ALLOW	00008	G:

Description:

Options

The first column is the Voucher Charge Type, the second column refers to the status of the charge type (ALLOW or DISALLOW), the third column is the expense code; and the fourth column is the account number.

Enter the desired values under each column for the Voucher Types.

Batch Processes

Payroll Voucher - sdbp_pay_voucher.pay_voucher;

Processes approved payroll vouchers which have not yet been posted. Once a payroll voucher is successfully processed, it is marked as posted.

Timekeeping Module

Fields

Next Approver Field

Designate approvers for Timesheet records in the Approval Limits module of the Administration subsystem under Approvals and Routes.

Code Tables

Code Table 310: Supervisor Title

Supervisor field - Define the supervisor titles to be used for various records. These codes define a supervisory position, not a specific person. Some examples of titles are Head Supervisor, Maintenance Supervisor, and Foreman.

Business Rules

Craft Rates Rule

Define Craft codes along with associated wage rates and expense codes.

Craft	Rate	Reg Expense	Prem Expense
ADMIN	25	00003	00004
APPRN	17.5	00003	00004
CARP	20	00003	00004
CUST	18.50	00003	00004
ELEC	24.50	00003	00004

Craft

Classify job types in the Craft field. Examples are ENG for engineer or MECH for mechanic.

Rate

This parameter sets the wage rate for the Craft listed.

Reg Expense

This parameter sets the expense code that the system will charge the employee's regular (i.e. non-premium) labor charges to.

Prem Expense

This parameter sets the expense code that the system will charge the employee's premium (i.e. Overtime) labor charges to.

(i.e. Overtime) labor charges to.

Holidays Rule

This rule defines holidays for any period of time as determined by the user. The holidays are used in conjunction with the Timekeeping Editchecks rule.

Holiday

Enter the description for the holiday in this column.

Date

Enter the date of the holiday in this column, in 'MM/DD/YYYY' format.

Charge Type

Enter H to indicate a holiday. This is the only option.

Charge Number

Not used.

Shift Diff

Not used.

Labor Burden Multipliers Rule

Associate labor burden rates to employees. These costs will be applied to the craft labor rates and rolled up in the system.

Process Type

This is a 20 character free form field. Enter all of the process types that you want to charge pay groups to.

Pay Group

Enter the group that is responsible for the process type listed. These fields reference Code Table 46.

Multiplier

This is the value that is used as the burden multiplier.

Expense Code

Enter the valid expense codes that should be charged for the corresponding pay groups.

Labor Type

Enter a Labor Type. PREMIUM or REGULAR.

Labor Costing Markup Rule

Apply additional markup transactions to labor costs based on the Area being charged for the work. If a timesheet charge is against an Area other than the Employee's Area on the Timesheet header, the markups for that Area will be included in the Account Log transactions and rolled up in the system.

Charge Area	Markup 1	Markup 2	Markup 3	Markk
DEFAULT	1.3	1.3	1.3	SCDC
MARKUP1	1.1	1.2	1.3	SCDC
MMY	1.2	1.3	1.4	SCDC

Charge Area

Choose an Area from the List of Values or enter Default to have the additional markup transactions applied. Any Area not listed will be processed with the Default markups. If a markup is not to be used with the Area, enter a markup rate of zero or leave blank.

Markup 1, 2, 3

Enter the markup rate (multiplier) to be used for each of the three available Labor Markup transaction types. You can enter values of zero or greater up to 9.99 (999%). Enter rates in fractions (i.e., .25, .10, 1.2).

Markup 1, 2, 3 Exp

For each corresponding Labor Markup transaction type, enter the Expense Code to be used for the Labor Markup transaction type. The Lists of Values for these fields reference the EXPENSE CODES Business Rule.

Labor Costing Wage Rates Rule

Determine where the wage rate is drawn from for labor costing. Wage rates can be drawn from the Employee Wage Rate view in the Employee module or from the Craft Rates Business Rule. Only one option can be set to YES, and the other must be set to NO.

Wage Rate Rule	Option Status
BUSINESS_RULE	YES
WAGE_DETAIL	NO

Wage Rate Rule and Option Status

BUSINESS_RULE - Uses the Craft Rates Business Rule to retrieve wage rates.

WAGE_DETAIL - Uses the Employee Wage Rate detail record for the wage rates. Set only one WAGE RATE RULE value to YES to use as the wage rate source; set the rest to NO.

Overtime Standings Rule

Control Overtime Standing processing.

Key	On/Off	Date
AVERAGING BATCH WEEK START	ON	21-SEP-1998
TRACK EMPLOYEE OVERTIME	ON	N/A

The Overtime Standing Process is only used to track overtime worked. Work offered and refused is not taken into consideration when ranking employees. This rule also allows you to produce an overtime list for holiday overtime based on seniority. Note: This Rule is used with Reports 78, 79 and 80. Please consult Oracle Utilities Work and Asset Management before you implement this Rule.

Key, ON/OFF, and Date

AVERAGING BATCH WEEK START - This batch procedure is used to average the overtime employees worked by crew for the previous one week period. Employees who did not work during the previous week period are averaged in based on previous overtime worked. For more information, see the Resource Users Guide, Employee module.

TRACK EMPLOYEE OVERTIME - Enter ON to track employee overtime. N/A has been entered in the DATE column as this column is not applicable.

Scheduled Holidays

The Scheduled Holidays rule defines holidays the system uses when creating timesheets for employees flagged for automatic timesheet creation.

Business Rule SCHEDULED HOLIDAYS

Rule ID: SCHEDULED HOLIDAYS Configuration List Limit?

Desc: This rule is used to define Holidays for a Calendar Year(s) to be used for the creation of Timesheets for Employees flagged as "Automatically Create Timesheet". If an automatic timesheet Employee is scheduled

Comment: The format of the date should be entered as "MMDD/YYYY".

Holiday	Date	Charge Type	Charge Number	Ex
2ND HOLIDAY	03/11/2004	V	001	OC
ANOTHER HOLIDAY	03/23/2004	C	003X	OC
NEXT HOLIDAY	03/25/2004	H	TIMESHT	OC

Description:

If an employee is scheduled to work on the same day as a scheduled holiday, the Timesheet line item will be created using the Charge Type, Account and Regular Expense Code defined for the holiday. Shift and Differential information will come from the appropriate Employee record.

Shift Differential Rates Rule

Determine valid shift codes and shift differential rates.

Business Rule SHIFT DIFFERENTIAL RATES

Rule ID: SHIFT DIFFERENTIAL RATES Business List Limit?

Desc: This rule is used to determine valid shift codes and shift differential rates.

Comment: The first column will contain valid shift codes. The second column will contain the shift differential which is either a straight dollar Adder or a percentage Multiplier (the value in this column is to be numeric or null).

Shift Code	Differential	OT Multiplier	Calculation
01	1	YES	Adder
3	1.25	YES	Adder
AA	1	YES	Adder
ABC	.75	NO	Multiplier
CX	1	YES	Adder
MLT	.05	YES	Multiplier

Description:

Shift Code

Enter the SHIFT CODE which is the definition of hours for an employee's scheduled period of work.

Differential

Enter the DIFFERENTIAL which is the additional hourly amount to be paid employees working the defined shift hours. This amount is added to the employee wage rate when using the Labor Costing Premium Multiplier Rule.

Example: An electrician makes \$25.00/hour, plus \$1.00 if he works the night shift. His regular rate with Shift Differential is \$25.00 + \$1.00 = \$26.00. If he works overtime at time and a half, his wage rate would be \$39.00 (Wage Rate of \$25.00 + Differential of \$1.00 = \$26.00) x Premium Multiplier of 1.5 = Hourly Rate of \$39.00.

OT Multiplier

If the OT Multiplier is set to Yes, then the calculations for premium shift amount will include the OT Multiplier: Premium Shift Differential * Multiplier * OT Multiplier * (Premium Hours - Comp Time Hours). If set to No, then the calculations for premium

shift amount will NOT include the OT Multiplier: Premium Shift Differential *Multiplier * (Premium Hours - Comp Time Hours).

Calculation

The differential can be added to the wage rate or multiplied by the wage rate. Enter Adder or Multiplier in this column to define how the system should calculate the values.

Timekeeping Authority Rule

Use this rule to define which users can access and maintain timesheets, leave requests, and employee records. This rule only controls who has access to the records, approval authorization is controlled in the Approval Limits module.

Note: A supervisor defined in this module does NOT correspond to the Supervisor fields defined by code table 310.

Username

Enter individual Usernames to set an authority level for access to Employee records, Timesheets, and Leave Requests. Anyone not listed will have the DEFAULT authority. By setting the USERNAME column to DEFAULT and the AUTHORITY column to EMPLOYEE, all users will be granted employee level authority without your needing to identify them explicitly.

Authority

The Authority column defines the scope of a users' authority. The authority levels include: Employee, Supervisor, Superuser and Payroll.

EMPLOYEE - User can only view or modify their own timesheet or employee record. Org Level does not apply.

SUPERVISOR - User can view or modify their own records and records of members of the Org Level entered. The Org Level value is used to widen the scope of the Supervisor authority. Set the value to Department, Area, or Crew, and the system limits the corresponding username to have access to other user's records who share the same Department, Area or Crew on their EMPLOYEE record. If you enter TITLE as the Org Level, the username is limited to see the user's records who are on the same CREW module record with the username. This allows Supervisors to approve timesheets for multiple crews (any crew that they are on).

SUPERUSER - User can view or modify any record. Org Level does not apply.

PAYROLL - User can view or modify any record, as well as override or adjust Compensatory Time Accrual calculations. Org Level does not apply.

For example, If BIGBOSS is entered under username in this business rule with the Authority set to Supervisor, and the Org Level set to Title, the system provides him access to the records for all users who are on the same CREW module records as BIGBOSS. If the Org Level is left blank or set to Crew the system provides BIGBOSS with access to the records of every user who has the same Crew entered on their EMPLOYEE module record as he has on his Employee record.

Org Level

The Org Level value is used to widen or narrow the scope of the Supervisor authority. See above for valid values and definitions.

Override

The override value is only used for those with the Supervisor or Superuser authority to temporarily promote them to Superuser or Payroll authority. Enter Superuser or Payroll in the Override column to give this authority to a user (to substitute for a supervisor who is on vacation, for instance). Filling in this value does not modify the authority of any other user. It can be changed or cleared later to restore the user to their original authority.

Timekeeping Charge Types Rule

Controls which Charge Types are valid in the Timekeeping module.

Charge Type	Status	Lookup	Reference ID
A	ALLOW	REFERENCE ID	
C	ALLOW	LEAVE	LEAVE
R	ALLOW	SERVICE REQUEST	
S	ALLOW	LEAVE	LEAVE
V	ALLOW	LEAVE	
W	ALLOW	WORKORDER	

Charge Type

Enter information into the Charge Type column. These values should be a single, unique character such as A for Account or S for Sick Leave.

Charges based on an Account Number use the Reference ID field as the Charge Number. Any Account Number you wish to directly charge time against must have a Reference ID. For more information regarding Reference ID's, please refer to the Account section of the Resource User Guide.

Status

The STATUS column of each Charge Type must be set to ALLOW or DISALLOW to allow or disallow charging time to that item.

Lookup

The LOOKUP column determines which database table is used to validate the associated Account Number at the time labor charges are entered.

Reference ID

The REFERENCE ID column contains an optional default Account Number. If you enter a value into this column, when a user charges time against this Charge Type, the Account Number entered here will default on the Timesheet and can not be overridden. This processing applies to charge types such as Sick Leave where you would not want users to enter any Account Number for sick time. If the entered Account Number is deactivated or deleted from the Account module, users will not be able to use the associated Charge Type.

Timekeeping Comp Time Request Rule

This rule determines if the Comp Time Request view displays on the Views list in the Timesheet module.

The screenshot shows a configuration window titled "Business Rule TIMEKEEPING COMP TIME REQUEST". It includes fields for Rule ID (TIMEKEEPING COMP TIME REQUEST), Business, Parameter, and Limit?. The Description field contains: "This rule determines if the Comp Time Request view is displayed on the timesheet module." Below this is a table with two columns: "Comp Parameters" and "Comp Options". The first row shows "DISPLAY COMP TIME REQUEST" with a value of "YES". A Description field at the bottom contains: "This determines if the Comp Time Request view is displayed on the timesheet Views list."

Comp Parameters and Comp Options

The default setting is YES, which allows the view to display. When the Comp Time Request Option is set to NO, the view is hidden from all users.

Timekeeping Copy Options Rule

Control whether or not the system will allow users to enter future pay period when using the Copy Single Timesheet Option of the Timesheet Wizard.

The screenshot shows a configuration window titled "Business Rule TIMEKEEPING COPY OPTIONS". It includes fields for Rule ID (TIMEKEEPING COPY OPTIONS), Business, Parameter, and Limit?. The Description field contains: "This rule determines the timekeeping copy parameters." Below this is a table with two columns: "Copy Parameters" and "Copy Options". The first row shows "COPY TO FUTURE PAY PERIODS" with a value of "ALLOW". A Description field at the bottom contains: "This determines if the copying of timesheet in the future pay period will be allowed."

Copy Parameters and Copy Options

COPY TO FUTURE PAY PERIODS - The Copy Options column must be set to ALLOW or DISALLOW. If set to ALLOW, future pay period dates can be entered on the Copy Information From and Copy Information To screens of the Timesheet Wizard. If set to DISALLOW, the system will not allow dates that are not within the current pay period.

Timekeeping Editchecks Rule

Determines whether or not edit checks for timekeeping verification of pay codes, hours, leave type, etc. is to be executed.

The screenshot shows a configuration window titled "Business Rule TIMEKEEPING EDITCHECKS". It contains the following fields and options:

- Rule ID: TIMEKEEPING EDITCHECKS
- Business: Business
- Parameter: Parameter
- Limit?:
- Desc: This rule determines whether or not edit checks for timekeeping verification of pay codes, hours, leave type, etc. is to be executed.
- Comment: (Empty text area)
- Type and Option Status table:

Type	Option Status
CHECK NEGATIVE REGULAR HOURS	OFF
DTA	OFF
LEAVE HOURS	ON
MODIFY APPROVE OR POSTED TIME	ALLOW
RESTRICT EMP BY CREW ON C&C	ON

Description: Checks whether timesheet's should have enough Regular hours to be backed-out.

Type and Option Status

CHECK NEGATIVE REGULAR HOURS - When this rule key is set to ON the Timesheet form validates that there is an existing Timesheet line item to allow an offset line item entry to the same charge number with a negative value less than or equal to the existing line item. When the key is set to OFF, the form allows a negative hours line item to be entered on the timesheet without the same charge number with a value greater than or equal to the negative value being entered. The Default is ON.

DTA - Special DTA (Distributed Time and Attendance) edit checks.

LEAVE HOURS - This will verify if there is enough available leave hours.

MODIFY APPROVED OR POSTED TIME - When this key is set to Disallow, only users with the timekeeping authority "PAYROLL" can modify timesheets in Approved or Posted status. If this rule key is set to Allow, users with timekeeping authority SUPERVISOR, SUPERUSER and PAYROLL are able to modify APPROVED and POSTED timesheets.

RESTRICT EMP BY CREW ON C&C - If this rule key is set to ON, the Employee list of values in the Cost and Closeout field are restricted to only those employees that are assigned to the specified Crew. When the Crew field is cleared, system will also clear the Employee field. If the key is set to OFF, the Employee list of values is open to all Active Employees.

Timekeeping Labor Earning Type Rule

Determine the Earnings Code values for Regular and Premium Type time, the Earnings Code Type, Multiplier (%) and/or Adder (\$), and the Overtime Rate Multiplier associated with each Earning Code that can be applied to the employee's base pay rate and hours when calculating Actual Labor Costs and Payroll data.

Business Rule TIMEKEEPING LABOR EARNING TYPE

Rule ID: TIMEKEEPING LABOR EARNING TYPE Business List Limit?

Desc: This rule determines the Earnings Code values for Regular and Premium Type time, the Earnings Code Type, Multiplier (%) and/or Adder(\$), and the Overtime Rate Multiplier associated with each Earning Code

Comment: The Multiplier represent a Percentage (%) value that allows numeric definition of at least 5 places to the right of the decimal. The Adder represents a Dollar value with 2 decimal palces (\$0.00).

Earning Code	Code Type	Multiplier	Adder	OT M
135	Regular	1.5		
135OT	Premium			1.5
BYBADD	Both		2.50	1.5
BYBMUL	Both	1.10		1.5
BYBWHL	Both	1.10	2.50	1.5
INDR	Both	3.3		
LEAVE	Regular			
MAV	Premium			1.5

Description

Earning Code

Use this column to label the Earnings Code. Earnings Codes defined here display on the Earnings Codes Lists of Values on the Timesheet, Timesheet Wizard, and elsewhere in the system when time is entered.

Code Type

Indicate if the supplemental Earnings Code is to be used for Regular time, Premium time, or Both. For hours entered on a timesheet, only one premium code or one regular code can be selected at a time. For additional hours with different codes, a separate entry must be made on the timesheet. You can assign the OT Rate Multiplier to a Both type Earnings Code. The system applies the OT Rate Multiplier only to the Premium Amount and not to Regular Amount, even when the Code type is set to Both.

Multiplier

The Multiplier represents a percentage (%) value that allows numeric definition of at least 5 places to the right of the decimal (1.5%=.015). An Earnings Code can be defined with a Multiplier, with an Adder, or with both.

Adder

The Adder represents an hourly dollar value with 2 decimal places (\$0.00). The Adder cannot be a negative number. The system uses the Adder to increase the employee's regular or premium pay

OT Multiplier

The system uses the OT Rate Multiplier to calculate the Revised Base rate when calculating Premium Time. The Revised Base is calculated before the Earnings Code Adder and Multiplier is applied. Note: If timesheets have not been posted or if costs have not been rolled up when an Earnings Code value is changed, items referencing that Earnings Code will use the new rate when processed.

Variable Expense Codes Rule

Rule	Option
DISPLAY EXPENSE CODES	YES
FORCE UNIQUE EXPENSE CODES	NO
OVERRIDE EXPENSE CODES	NO

This rule determines how expense codes are handled during stock checkout, checkout request, planning work order task materials and labor, and in the Timekeeping module. Regardless of the settings in this rule, any desired changes to expense codes can only be made before costs are actualized. Once actual costs are applied, the expense code on the record cannot be changed.

Rule and Option

DISPLAY EXPENSE CODES - If you enter YES as the option, the system will display the Regular and Premium Expense Code fields on the employee Timesheet, and the Expense Code field on the Issue Ticket for stock checkouts based on Work Orders. Enter NO and the field is not displayed.

FORCE UNIQUE EXPENSE CODES - If you enter YES for this option, work order time charges for the same craft must have the same expense codes. The default setting is YES.

OVERRIDE EXPENSE CODES - Enter YES or NO in the OPTION column to allow or disallow users to change expense codes on timesheets, issue tickets for stock checkout, stock checkout requests, and material and labor detail records on work order tasks.

Entering YES in the OPTION column has the following implications:

- Materials planners will be able to overwrite the default expense codes for the Materials view of the Work Order module in the Maintenance subsystem. The system defaults this information from expense code associated with the Stock Code and Storeroom.
- Employees responsible for creating Issue tickets for stock item checkouts will be able to change the associated Expense code.
- The system will display the Regular and Premium Expense Code fields on the employee Timesheet, and the Expense Code field on the Issue Ticket for sock checkouts based on Work Orders. This includes expense codes that have been provided by planners.
- Labor planners will be able to overwrite the default expense codes for Regular and Premium labor on Work Order Tasks. The system defaults this information from the Craft associated with the Work Order Task.

-
- Workers who enter their own time into the Timekeeping module of the Maintenance subsystem, will be able to change the Regular and Premium labor information brought over from the Work Order Task on timesheet entries based on Work Orders. This includes expense codes that have been provided by planners.
 - Supervisors who review timesheets will be able to change the Regular and Premium labor information brought over from the Work Order Task on timesheet entries based on Work Orders. This includes expense codes that have been provided by planners and/or changed by employees on their timesheets.

Combining the Rules:

To keep anyone from changing expense codes:

Display Expense Codes = NO

Force Unique Expense Codes = YES

Override Expense Codes = NO

To allow only Planners to use variable expense codes:

Display Expense Codes = NO

Force Unique Expense Codes = YES

Override Expense Codes = YES

To allow charges for the same craft to use different expense codes:

Display Expense Codes = YES

Force Unique Expense Codes = NO

Override Expense Codes = YES

Copy Record

TIMESHT - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Approve All Timesheets

Grants access to the Approval All Timesheets action in the Timekeeping module.

Cost and Closeout

Adds the Cost and Closeout action to the user's home page action list.

Route Timesheet for Approval

Grants the ability to set the statuses of multiple timesheets to pending approval. Selecting the action from the Timesheet module on any one of the time period views sends one alert per timesheet in that period to the designated approver.

Timesheet Wizard

Grants the ability to use the Timesheet Wizard from the home page.

Batch Processes

Auto Create Timesheets - `sdbp_auto_create_timesheet.main`;

Triggers functionality where the system automatically creates timesheet records for employees as designated on their Employee record. The system can be configured to automatically create timesheets for employees who work a fixed schedule by checking the Automatically Create Timesheet? Indicator in the Auto Timesheet Schedule view in the Employee module.

Cost and Closeout - `smu_interface.sdbp_mu_interface (job_in, plant_in,'N')`;

Processes transactions entered in cost and closeout.

Leave Request - `sdbp_post_leave`;

Posts Leave Requests and creates timesheets for approved Leave Requests that have the Create Timesheet indicator checked and are in an open Pay Period.

Post Timesheet - `sdbp_post_timesheets.post_time`;

Posts timesheet information such as Leave, Regular Time etc. for Pay Periods and recalculates the balance. Once a Timesheet has posted for the Pay Period, the payroll status is set to Closed.

Reports

S_RPT066 - Payroll Report

Provides a summary of hours and wages for payroll.

S_RPT067 - Labor Expenditure Summary by Account Report

Provides a summary of labor costs by Account Number for a given Pay Period.

S_RPT068 - Labor Distribution by Account Report

Provides labor costs and hours by Account Number.

S_RPT069 - Labor Distribution by Employee Report

Provides labor costs and hours by Admin. Department.

S_RPT079 - Overtime Standing Report by Crew

Lists overtime standing information for each crew.

S_RPT080 - Overtime Standing Report by Zone

Lists overtime standing information by overtime zone.

S_RPT139 - Employee Timekeeping Report

Provides a summary of hours and wages for payroll.

Charts

S_CHT138 - Timekeeping Analysis

Timesheet Hours for the current year and the previous year. The data can be filtered further by Plant, Department, Area, Earnings Code, Charge Type, and Pay Type.

Purchasing Subsystem

Vendor Code Structure Module

Use the Vendor Code Structure module to define how vendor codes appear in the Vendor module. The system displays all Vendor Code fields throughout the system using the defined structure.

Determine the number of segments, segment names, lengths, whether the segments are required, whether the second segment should be sequenced, and the delimiter to separate the two segments.

Fields

Segment Name

If your organization will not use multiple locations for vendors, leave segment 2 blank.

The user has the ability to create the segment names that will show in the vendor module. There are two segments that will be used to create the vendor code. The first segment name is required by the system. This is the general Vendor code used in all processing. Users who want to also establish different locations for each vendor can set a second segment for the Location Code.

Avoid the use of the special characters ', ", &, or % as they may result in processing errors.

Length

The Length field indicates the maximum number of characters that can be entered in the segment. If a user enters less than the maximum, the system displays the positions for the other characters as blanks. The total length of the two segments cannot exceed 30 characters, and the character delimiter counts as a character.

Make sure that the length entered here is the same as the length entered for the table SA_Vendor in the Sequence Numbers module. If these numbers are different, the system will generate an error message when it tries to create a sequence number for the Vendor Code.

Sequenced?

You must check the Required box next to segment two before the sequence or length can be entered.

If this indicator is set, the second segment is sequenced when creating new location records for vendors. It is recommend that you DO NOT use automatic sequencing for the second segment so that you can include an intelligent identification system for each Location. For example, you can have a Vendor ID (0000000003 - Grainger) which has multiple location sites (001 - Anaheim, 002 - Chicago, 003 - Detroit).

The first segment can be made system generated by configuring the Sequence module for

the table name SA_VENDOR.

Required

The first segment is always required by the system as it identifies the vendor code.

When this box is checked for the second segment the system is able to manage vendors by multiple locations. Checking this box also enables the Add Location action in the Vendor module.

Delimiter Character

The Vendor Code is a combination of segment 1 and segment 2. You can use the Delimiter field to determine what kind of character the system will show between segments of the Vendor Code. If no delimiter is defined, the segments are simply combined with no separation.

The lines between the Required check boxes and the Delimiter Character field do not represent anything and should be ignored.

Vendor Module

Fields

Sequence No.: Vendor Code

The record number is comprised of a unique ID (Ex. "VDR002"). Vendor codes numbers are typically set to be created manually.

TABLE NAME - SA_VENDOR - The sequence number generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

E-Mail Purchase Orders to Vendors (Characteristics View)

If you want to allow your Buyers to e-mail Purchase Orders and/or Blanket Contracts to Vendors, you must enter Purchasing as a Characteristic Type and the corresponding value as the Characteristic.

Business Rules

Payment Terms Rule

Terms Code	Description	Days	Fixed Date	Dis
10	NET 10/2%	10		2
20	NET 15/5%	15		10
30	AT INVOICE RECEIPT	0		

Define payment terms and the number of days before payment is due per term.

Terms Code and Description

Enter the codes to define your payment terms, and define the code in the Description column.

Days

Enter the number of days that the system should use to calculate the invoice due date based on the vendor date entered on the invoice.

Fixed Date

If a vendor has arranged for an invoice due date to be the same each month, enter the day into the this column. For example, if 20 is entered in this column, the due date would be the 20th of every month.

Discount %

Enter any discount that might be given for using a certain payment term.

Vendor Options Rule

Parameter	Status	Value
PERFORMANCE CURRENT RATING	ON	3
PERFORMANCE GRACE PERIOD	ON	0
PERFORMANCE QUALITY ATTRIBUTES	ON	

Define parameters used by the Vendor module in rating vendor performance.

Parameter, Status, and Value

PERFORMANCE CURRENT RATING - Determines the number of months to be used in the batch calculations of Vendor Performance. Enter ON in the Status column to enable Vendor Performance calculations. Enter the number of months to be considered in the Value column.

The rating is calculated based on delivery dates that fall between one full month prior to the current date minus the number of months entered in the Value column.

Note: The Performance view is only visible if this rule key is set to ON.

PERFORMANCE GRACE PERIOD - Determines the number of days after the Promise Date before a delivery is considered to be late. Enter ON in the Status column to enable Grace Periods. Enter the number of grace days in the Value column. Only one grace period can be set for all shipments.

PERFORMANCE QUALITY ATTRIBUTES - Determines whether or not the system will use the attributes and point values defined in the VENDOR PERFORMANCE ATTRIBUTES Business Rule.

When this rule key is ON, the quality rating is based on the score received for each shipment from the vendor. When the rule key is OFF, the quality rating is based on PO line item, not shipment, being received without the discrepancy indicator being set.

VENDOR NAME - If your organization does not use two part vendor, as set in the Vendor Code Structure module, this rule key does not apply. Determines how the vendor name is displayed in lists of values and wherever else the vendor name is displayed throughout the system.

If Two Part Vendor is in use, the default value for this VENDOR NAME rule key is LOCATION. The Status setting is ignored. If you want to alter the default, options include the following:

VENDOR - If the parameter is set to VENDOR, then the vendor name is displayed as the actual vendor name. This is the value in the sa_vendor.vendor_name column.

LOCATION - If the parameter is set to LOCATION, then the vendor name is displayed as the location name only. This is the value in the sa_vendor.location_name column.

VENDORLOC - If the parameter is set to VENDORLOC, then the vendor name is displayed as "vendor name - location name" using the same related columns as noted above.

The vendor value comes from the sa_vendor.vendor_name column. The location value comes from sa_vendor.location_name column.

Vendor Performance Attributes Rule (Performance View)

Business Rule VENDOR PERFORMANCE ATTRIBUTES

Rule ID: Business Limit?

Desc: This rule contains the attributes and associated point value used for baseline vendor performance.

Comment:

Quality Attribute	Point Value
R01 PACKAGING	5
R02 NO PO	10
R03 DAMAGE	10
R04 BUY AMERICAN ACT	10
R05 PO COMPLIANCE	10
R06 SHELF LIFE EXPIRED	10
R07 CLEANLINESS	5
R08 DIMENSIONAL	10
R09 APPROVED MANUFACTURER	10
R10 CERTIFICATIONS	10
R11 DIMENSIONAL VERIFICATION	10
R12 TRIR INSPECTIONS	10
R13 MISCELLANEOUS	5

Description:

Specify the 'Best Price Multiplier' for given performance ranges. You can establish as many ranges as needed, but the Ranges can not overlap and they must be whole numbers. When the multiplier is more than 1 the vendor's quoted price on an RFQ is increased by the amount of the multiplier. This is a way to weight non-performing vendors.

Determine the attributes and associated point values used for vendor performance rating.

Quality Attribute

Enter Quality Attributes that describe the criteria that will be used to determine whether or not a vendor has delivered items or services properly. Typical examples are Packaging, Damage, Delivery, PO Compliance, and Cleanliness.

Point Value

Assign a Point Value, based on the importance of Vendor compliance, to each attribute.

The system uses the attributes and point values when calculating each vendor's performance rating. These values are then used to determine the vendor's overall performance rating.

Vendor Performance Ranges Rule (Performance View)

Business Rule VENDOR PERFORMANCE RANGES

Rule ID: Business Parameter Limit?

Desc: Used to specify "Best Price Multiplier" for given performance ranges.

Comment: The user has to make sure that ranges don't overlap. Ranges should be whole numbers only. Subsequent ranges should be named Range2 Range3 etc.

Range	Lower%	Higher%	Multiplier
RANGE1	0	50	1.1
RANGE2	50	75	1.05
RANGE3	75	100	1.0

Description: Best Price Multiplier for specified range.

Subsequent ranges should be named Range2 Range3 etc.

Range

Ranges should be named Range1, Range2, Range3, up to the total number of ranges to be defined.

Lower %

Enter the lower percentage value for the Total Vendor Performance for the range.

Higher %

Enter the higher percentage value for the Total Vendor Performance for the range. Since this value is a 'less than' value, enter 101% to include vendor performance rating of 100%.

Multiplier

Enter the multiplier value for the range. Define multiplier values to increase bids from vendors with lower vendor performance ratings.

Code Tables

Code Table 22: Vendor Characteristic Types (Characteristics View)

Characteristic Type field - Define vendor characteristics. The List of Values for the Characteristic field is limited by your selection in this field. Values for the Characteristic field should be linked to this code table.

Code Table 43: FOB

FOB (Free On Board) field - Define codes to designate from which point the Buyer pays for the delivery charges. This code table is typically populated with Vendor and Buyer locations.

Code Table 56: Vendor Characteristics (Characteristics View)

Characteristic field - Linked Code table when 'General' is entered in the Characteristic Type field.

Code Table 68: Vendor Classification Types (Characteristics View)

Linked to Vendor_Class in Code Table 22.

Code Table 122: Commodity Category Codes (Commodities View)

Category field - Commodity information can be especially helpful when trying to locate a specific stock code. Commodity Codes categorize and sub-categorize stock items, allowing you to create and maintain a descriptive structure used to quickly identify the

type of part you are looking for, and from a much shorter list of stock items, locate the right one.

A sample Category Code might be Electrical or Instrumentation.

Link

Each Category Code points to its own Commodity Name Code Table. This Link field is where the Commodity Name Code Table number would be inserted. For example, if 'M' (for Mechanical) is chosen as the Commodity Code, the 'linked' table for Commodity Names would only contain values that pertain to the 'M' category.

Code Tables 122, 123, 124, 125, 128, and 129 work in conjunction to define a Commodity Code for a Stock Item.

Code Table 123: Commodity Composition (Commodities View)

Composition field - Physical matter types are populated in this code table. Some examples might be Aluminum, Iron, Rubber, etc.

Code Table 115: Auditor Codes (Approved Vendors View)

Auditor field - Define codes to identify valid auditors for Vendors. Examples include Primary Vendor Manager for Chemical Providers, Primary Vendor Manager for Fuel Providers, Primary Vendor Manager for Mech Parts and EQP Providers, etc.

Code Tables 173, 174, 177, 178, and 179: Vendor Capability Code Segments 1-5 (Capabilities View)

Capabilities View - These code tables identify the types of products a particular vendor can supply. These tables serve as a useful means of searching for vendors where the capabilities are known. A capability is the product or service the Vendor provides, a characteristic (code table 56) is descriptive of the type of business they conduct.

The following web sites govern ways to breakdown vendor capabilities and characteristics:

NAICS and SIC <http://www.census.gov/pub/epcd/www/naics.html>

SIC http://www.wave.net/upg/immigration/sic_index.html

UNSPSC <http://www.eccma.org/unspsc/>

Code Table 175: Vendor Evaluation Grades (Evaluation View)

(Overall Rating, Delivery, Price, and Rejection Rate)

Overall Rating field - Define a rating system to evaluate vendors. Typical entries for this code table might be 'B', below average, 'A', average, 'E', excellent performance, etc. This code table is used for Overall Rating, Delivery, Price, and Rejection Rate LOV.

System Code Table (Cannot be modified)

Code Table 65: Purchasing Vendor Characteristics (Characteristics View)

Characteristic field - Linked code table when 'Purchasing' is entered in the Characteristic Type field. If you want to enable the ability to email purchase orders or blanket contracts to the vendor, make sure that EMAIL PO and/or EMAIL BC are entered as values for this characteristic.

Copy Record

VENDOR - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer

to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Set Vendor Auto Pay Indicator

Grants the ability to check or uncheck the Auto Pay Ind. box on Vendor records to designate or remove Auto Pay Vendor status.

Batch Processes

Vendor Performance - sdbp_vendor_performance.vendor_performance;

Supports the gathering of Vendor Performance statistics. This procedure performs the following:

- Identifies the processing parameters for the Current Rating Period for Active Vendors.
- Updates Quality Performance data based on changes since the last batch run.
- Updates Delivery Performance data for new transactions.
- Updates Quality Performance data for new transactions.

Charts

S_CHT1136 - PO By Vendor - Count of POs

A count of Purchase Orders for the current year and previous years. The data can be filtered further by Plant and Vendor Name. Other filtering options, such as Buyer, PO Type and PO Status, are available in the Chart Field List.

S_CHT135 - PO By Vendor - Total Amount

Shows the Total Amount of Purchase Orders for the current year and the previous year. The data can be filtered further by Plant and Vendor Name. Other filtering options, such as Buyer, PO Type and PO Status, are available in the Chart Field List.

Reports

S_RPT142 - Deficient Vendors Report

Displays Vendors who have a Composite Rating of less than 90% and who have made at least 10 Deliveries (both for the Current Period). It also contains a detailed listing of the Vendor's Late Deliveries and/or Quality Deficiencies.

S_RPT201 - Purchase Order Listing Report - Grouped by Vendor Code

Displays a summary of all Purchase Orders Grouped by Vendor Code.

S_RPT207 - Purchase Order Report - Vendor Copy

The purchase order that is sent to Vendor's when orders are made.

S_RPT200 - Purchase Order Vendor Report

Displays a Vendor summary of all Purchase Orders within a Date Range.

S_RPT018 - Storeroom Value by Vendor

Lists total storeroom values by Vendor from the storeroom module.

S_RPT143 - Superior Vendor Performance Data

Displays Vendor Performance Data for vendors with a Composite Rating of at least 98% and who have made at least 10 Deliveries (both for the Current Period).

S_RPT022 - Vendor Characteristics Report

Lists Vendors and their characteristics from the Characteristics detail in the Vendor module of the Purchasing subsystem.

S_RPT213 - Vendor Classification Activity Report

Summarizes Purchase Orders issued against Blanket Contracts by Vendor Class and Vendor Name.

S_RPT124 - Vendor Label Report

Outputs Vendor mailing label data for use with Avery 5160 labels.

S_RPT021 - Vendor Listing Report

Lists Vendor information created in the Vendor module of the Purchasing subsystem.

S_RPT144 - Vendor Performance by Buyer

Displays the number of On Time and Late Deliveries and the On Time Percentage for each Vendor, grouped by Buyer. It will also display their Year To Date figures.

S_RPT145 - Vendor Performance Data

Displays Vendor Performance Data.

S_RPT141 - Vendors with 3 or More Deficiencies

Displays Vendors who have 3 or more Quality Deficiencies along with a list of the deficiencies.

Requisition Module

Fields

Sequence No.: Requisition Number

The record number is comprised of a unique ID (Ex. "0200683"). Requisition record numbers must be system generated. Manual creation of these record numbers could result in critical system errors when records are created from other records or in batch procedures.

TABLE NAME - SA_REQUISITION - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Approval Route Field

Designate approvers for Requisitions the Approval Limits module of the Administration subsystem under Approvals and Routes.

Buyer field

Make sure to populate the Buyer module with codes for Buyers responsible for purchasing documents.

Ship To field


The List of Values for the Ship To field is controlled by active storerooms entered in the Storeroom module of the Resource subsystem.

Currency (Buyer Data View)

Currency Codes are defined and updated in the Currency Exchange Rates module.

Business Rules

Alerts Rule



Alert	Recipient
BACKORDERED ITEMS HAVE ARRIVED	REQUESTOR
PARTS HAVE ARRIVED	REQUESTOR
PO ITEM RECEIVED	REQUESTOR
WORK ORDER HAS BEEN APPROVED	REQUESTOR

This business rule identifies system alerts that are available and who should receive the alert. New Alert types cannot be created.

Alert and Recipient

BACKORDERED ITEMS HAVE ARRIVED - Work Orders and Checkout Requests - Enter REQUESTOR in the Recipient column to have an alert sent to the requestor when backordered items come in. The requestor who's Issue Ticket Report has been printed will receive the alert.

PARTS HAVE ARRIVED - Work Order - Enter REQUESTOR or PLANNER in the RECIPIENT column to have an alert sent to the requestor or planner of a work order with a direct purchase is received in the Receiving module. The default is REQUESTOR. When this is set to PLANNER the alert is sent to the planner indicated on the work order task, not on the work order.

PO ITEM RECEIVED - Requisition - Enter REQUESTOR in the PO ITEM RECEIVED column to have an alert sent to the requestor identified on the Requisition when the requested PO item is received.

WORK ORDER HAS BEEN APPROVED - Work Order - Enter REQUESTOR in the RECIPIENT column to have an alert sent to the work order requestor when approval has been processed for the work order.

WO FINISH WITH OPEN PO OR REQ - Purchase Order, Requisition - Enter the person who should receive an alert when a Work Order that references an open purchase order or requisition is set to Finished status. The Default setting is to BOTH.

Batch Purge Criteria Rule

Business Rule BATCH PURGE CRITERIA

Rule ID: BATCH PURGE CRITERIA Business Parameter Limit?

Desc: This rule defines criteria for batch purge processing.

Comment: Batch processing. Define rule keys to specify criteria for purging of data in batch jobs.

Batch Processing	Status 1	Status 2	Status 3	Status 4
▲ EVENT QUEUE STATUSES	FAILED	FAILED		
REQUISITION PO STATUSES	CLOSED	CANCELED		
▼ WORK REQUEST WO STATUSES	CLOSED	CANCELED	REJECTED	HISTORY
▼				

Description: Work requests associated to work orders in the statuses entered in the Status 1 - 4 columns are purged. For example, if the value in the Status 1 column is set to CLOSED, the system purges any work requests associated to work orders in CLOSED status.

Define the status values which determine when to delete obsolete data. Records are deleted when batch purge processing runs. Enter the applicable statuses in the Status 1, Status 2, and Status 3 columns for each record type. For example, for work requests, if the value in the Status 1 column is set to CLOSED, the system purges any work requests associated to work orders in CLOSED status.

Batch Processing

EVENT QUEUE STATUSES - Delete event queue entries that are in the statuses identified in the status columns.

REQUISITION PO STATUSES - Delete requisitions associated with purchase orders in the statuses identified in the status columns. Typically, Requisitions are considered unnecessary after the PO has been CLOSED or CANCELED.

WORK REQUEST WO STATUSES - Delete work requests associated to work orders that are in the statuses identified in the status columns. Recommended options for Status 1 - 4 include work orders in CLOSED, CANCELED, HISTORY, or REJECTED status. Although it is possible, it is NOT recommended that you purge work requests associated to work orders in PLANNING, PENDING APPROVAL, APPROVED, ACTIVE or FINISHED status.

STATUS 1, STATUS 2, STATUS 3 - These columns indicate the statuses for the records that are purged. Status 1 is the prime status to be deleted. Status 2 and 3 are other desired statuses.

Batch Purge Parameters Rule

Batch Parameters	Days
ALERTS	1
AUDIT LOG	0
BATCH_MESSAGES	7
EVENT QUEUE	5
REQUISITIONS	9
WORK REQUESTS	0

Description
Alerts are those records generated by the system when a defined event occurs requiring user attention. Alerts may be accessed (per user) via the WorkFlow Agent. Purge processing compares the Alert Date to the current

As system data ages, it often becomes of little or no value to users. Purging old data regularly prevents tables from growing too large and helps maintain a quick system response time when querying those tables.

The Batch Purge Parameters Rule defines, per specific type of data, the age of a record before batch processes purges it. Note that the specific routines called for purging are already defined, purging either a single record at a time or a header record and its associated view, whichever is appropriate.

Batch Parameters and Days

ALERTS - Set the number of days the system should retain Alerts on the home page. Purge processing compares the Alert Date to the current date minus the number of days listed in the DAYS column, and deletes any messages that fall outside of that range.

AUDIT LOG - Set the number of days the system should retain Audit Log entries. Purge processing compares the date that the entry was made to the current date minus the number of days listed in the DAYS column, and deletes any messages that fall outside of that range.

BATCH_MESSAGES - Messages generated by batch processing and are stored as records in the Job Manager module so that you can easily access and review them at any time. Purge processing compares the Batch Message Date to the current date minus the number of days listed in the DAYS column, and deletes any messages that fall outside of that range.

REQUISITIONS - Purge Processing compares the PO Status Date (for status settings in the Batch Purge Criteria business rule) to the current date. When the result is greater than the number of days listed in the DAYS column, the Requisition is deleted from the system.

WORK REQUESTS - Purge Processing compares the Work Order Status Date (for status settings in the Batch Purge Criteria business rule) to the current date. When the result is greater than the number of days listed in the DAYS column, the work request is deleted from the system.

Credit Card Purchases Rule

Business Rule CREDIT CARD PURCHASES

Rule ID: Business Parameter Limit?

Desc: This rule controls whether or not direct purchase items may be paid for using a credit card.

Comment: To control which document types (such as Purchase Orders) may be charged against a credit card, list the document types in the "DOCUMENT TYPE" column and set the "OPTION STATUS" column to ALLOW or

Document Type	Option Status
PURCHASE ORDER	DISALLOW
REQUISITION	DISALLOW
WORK ORDER	ALLOW

Description: Allows user to charge direct purchases against a credit card.

Control which type of documents are valid for direct purchase items to be paid for using a credit card. Direct Purchase items can be paid for using a credit card number (associated with an Employee record) as the charge number.

Document Type and Option Status

PURCHASE ORDER, REQUISITION, WORK ORDER - Allows or prevents users from charging direct purchases against a credit card. Enter ALLOW to enable charging of direct purchases to credit card numbers or DISALLOW to prevent it for each document type.

Requisition to PO Rule

Business Rule REQUISITION TO PO RULE

Rule ID: Business Parameter Limit?

Desc: This rule determines whether Purchase Orders created from Requisitions will be created in CREATED, APPROVED or ISSUED status.

Comment: Enter CREATED, APPROVED or ISSUED in the "STATUS" column to establish if the status of a Purchase Orders created from a Requisition should be CREATED, APPROVED (the default) or ISSUED, respectively.

Rule	Status	On/Off
CHECK BUYER APPROVAL		ON
REQ_TO_PO_STATUS	CREATED	ON

Description:

Determine whether Purchase Order records created from requisitions will be created in Created, Approved or Issued status.

Check Buyer Approval

Enter ON or OFF in the "ON/OFF" column. The approval limit is always checked for the Requisition irrespective of whether the rule is ON or OFF. If the rule key is set to ON, the PO Approval limit is also checked. If it is set to off OFF only the requisition approval limit is checked.

Req_To_PO_Status

Enter Created, Approved, or Issued in the Status column to indicate which status Purchase Order records created from requisitions should be created in.

Purchasing Options Rule

Option	Status	Values
BOTH EDI/AUTOFAX WHO WINS		EDI
DEFAULT PRINT PO ITEM IND	OFF	
DISPLAY BLANKET RFQ EXP ACTION	ON	
ENFORCE APPROVED VENDOR	ON	
EXPEDITE ITEM DETAILS	ON	
LEAD TIME	ON	BUSINESS
RESTRICT ITEMS BY PO TYPE	OFF	
STORES LOOKAHEAD REQUIRED DATE		PO
TEMPORARY STOCK STOREROOM	ON	TMP

The Purchasing Options Rule defines processing options for the Purchasing subsystem.

Option, Status, and Value

ACCOUNTS REQUIRED ON PENDING - This rule determines when the system checks for valid account splits on purchasing records. When it is set to ON, changing to Pending Approval status triggers the validation. When it is set to OFF the system validates accounts when the record is changed to Approved status. The default setting is "ON".

BOTH EDI/AUTOFAX WHO WINS - This rule key determines whether EDI or Auto-fax will be used, if both are available methods to transmit purchasing documents.

DEFAULT PRINT PO ITEM IND - This rule key determines the default setting of the Print Line Item indicator when a Purchase Order is copied to a Change Order.

DISPLAY BLANKET RFQ EXP ACTION - When this rule key is set to ON the Export Blkt RFQ to File action is displayed on the Actions list in the Request for Quotes module. This action allows users to export the Blanket RFQ data to an Excel spreadsheet.

ENFORCE APPROVED VENDOR - This line determines if the approved vendor limitation will be enforced for purchasing documents during online and batch processing. When the status is set to ON, if any item on a PO (or other purchasing document) requires an approved vendor, as defined by the procurement level field, then the entire PO requires an approved vendor. The approved vendor requirement will be enforced when the PO is issued. Only users with an Approval Title with the document type AVOVERRIDE have the option of dismissing the requirement.

EXPEDITE ITEM DETAILS - This rule key determines whether or not there are item details for purchase expedite records. When the status is set to ON, the system provides a View to the PO Expediting module in the Purchasing subsystem. This view can be used for tracking partial shipments, and an informational version of the window is also offered as a view of the Purchase Order module in the Purchasing subsystem.

LEAD TIME - The lead time indicates whether the system will calculate a default Promise Date on Purchase Orders created through using batch processing and Blanket Contracts.

If the value is set to CALENDAR, all days are included in the calculation of the promise date.

RESTRICT ITEMS BY PO TYPE - The intention of this rule key is to allow or disallow the mingling of different stock code types on a single purchase order.

Note: Regardless of the rule key setting, any time a stock code is entered on a purchase order line item, the line item type must be "M" (Materials). This rule key only pertains to Purchase Order Type and Stock Item Type.

When the status is set to ON the system enforces restrictions on the combination of stock type and purchase order types that can be included together on purchasing documents. These restrictions are based on the following:

- Direct type stock items - Can only be added to P (purchase), B (blanket contract) and W (work order generated) type purchasing documents
- Inventory or Expense type stock items - Can only be added to S (stores replenishment type) purchasing documents
- This setting does not affect S and W type purchasing documents generated by Batch Processing.

When the status is set to OFF, you can combine stock types (Direct, Inventory, and Expense) and purchase types (B, P, S, V, and W) without these restrictions, however there are general restrictions which apply whether the rule key set to ON or OFF. Please refer to the following table for details:

Purchase Type	Blanket (B)	Purchase (P)	Services (V)	Stores Replenishment (S)	Work Order Generated (W)
Stock Types Allowed by Purchase Type	Expense Inventory Direct	Direct	Direct	Expense Inventory	Direct
Stock Types Not Allowed by Purchase Type	Phantom Consignment	Phantom Consignment Inventory	Phantom Consignment Inventory Expense	Phantom Consignment Direct	Phantom Consignment Inventory Expense
PO Line Types Allowed by Purchase Type	Materials Services Misc.	Materials Services Misc.	Materials Services Misc.	Materials	Materials Services Misc.

STORES LOOKAHEAD REQUIRED DATE - This rule key determines which date is used as the promised date for items on a purchase order. Set the key to PO to use the promise date on the purchase order header for every item. Set the key to PO ITEM to use the promise date from each individual purchase order line item.

TEMPORARY STOCK STOREROOM - If the storeroom is identified and this rule key is set to ON, direct purchase items are allocated to the original purchase order to ensure proper issuance of the material upon receipt. Only Active storerooms with Direct stock type can be chosen from the list of values.

Code Tables

Code Table 7: Location (Length = 10)

Deliver to Location field - Define codes to designate possible delivery locations within your organization. Typical entries include: "North side loading dock" or "Main Warehouse".

Code Table 23: Unit of Measure (Line Item (Detail) View) (Length = 4)

Unit of Purchase (UOP) and Unit of Issue (UOI) fields - Define units codes. These fields are used by the system to maintain quantities as parts are issued and new parts are received. You may, for instance, issue in units of each ('EA') but order in units of boxes ('BOX') where one box would contain 10 individual items. Code Table 23 enables you to define the different Units of Purchase and Units of Issue.

Code Table 26: End Use Code (Buyer Data View) (Length = 2)

End Use Code field - Define codes to identify where items for the requisition are to be used in the plant. Examples include: 'D' for Specific Department Usage, 'P' Plant Wide Usage, etc.

Code Table 43: FOB (Buyer Data View)

FOB (Free On Board) field - Define codes to designate from which point the Buyer pays for the delivery charges. This code table is typically populated with Vendor and Buyer locations.

Code Table 159: Federal Tax Codes (Buyer Data View) (Length = 1)

Federal field - The code can only be one character long and the Description should contain the percentage rate in the first six characters of the field.

Code Table 160: State Tax Codes (Buyer Data View) (Length = 1)

State field - The code can only be one character and the Description should contain the percentage rate in the first six characters of the field.

Code Table 161: Duty Codes (Buyer Data View) (Length = 1)

Duty field - The code can only be one character long and the Description should contain the percentage rate in the first six characters of the field.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Create Req from Blanket

Grants the ability to create a requisition from an active Blanket Contract record.

Create Shipping Memo

Grants access to the action which allows users to create a shipping memo from a requisition.

Create Templates from REQ

Grants the ability to create a template from a Requisition using the Copy Record action in the Requisition module.

Resend Approval Request

Grants the ability to resend an Approval Request using the Resend Approval Request Action in the Requisition module.

Batch Processes

Purge Requisitions - sdbp_purge_requisitions;

Enable or disable a batch job to purge Requisitions in PO Created status where the PO is in a certain status. The status and age are defined in the Batch Purge Parameters and Batch Purge Criteria Business Rules.

Requisition Template Status Check - sdbp_req_template_status_chk;

Allows you to automatically activate/de-activate Requisition Template records based on its duration values.

Metrics

S_MTRC3 - Total Lead Time - sdbp_metric_total_lead_time

This metric is to provide an average lead-time (in days) for the entire purchasing process (approved Requisition to first PO receipt). It provides a means to monitor and improve the total time (internal and external) required to receive items for an approved Requisition.

Reports

S_RPT054 - Requisition Report

This report is similar to the Purchase Order Report except space is provided at bottom for approval signatures and is typically used for internal routing purposes. Please refer to topics regarding the PO Report Constants and PO Report Status Codes Business Rules for more information on this report.

S_RPT215 - Requisition Report (by Vendor)

Summarizes open Requisitions by Vendor.

Purchase Order Module

Fields

Sequence No.: Purchase Order

The record number is comprised of a unique ID (Ex. "02001027"). Purchase order numbers must be system generated. Manual creation of these record numbers could result in critical system errors when POs are created from other records or in batch procedures.

TABLE NAME - SA_PURCHASE_ORDER- The sequence number is generated for this database.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Approval Route Field

Designate approvers for purchase orders in the Approval Limits module of the Administration subsystem under Approvals and Routes.

Buyer field

Make sure to populate the Buyer module with codes for Buyers responsible for purchasing documents.

Ship To field

The List of Values for the Ship To field is controlled by active storerooms entered in the Storeroom module of the Resource subsystem.

Currency (Buyer Data View)

Currency Codes are defined and updated in the Currency Exchange Rates module.

User-Defined

If you use user-defined fields in the Purchase Order module AND you use Multi-Step Receiving, you must make sure that both modules have the same user defined fields. Please refer to the Configuration Guide for User-Defined fields for more information.

Business Rules

Alerts Rule

Alert	Recipient
BACKORDERED ITEMS HAVE ARRIVED	REQUESTOR
PARTS HAVE ARRIVED	REQUESTOR
PO ITEM RECEIVED	REQUESTOR
WORK ORDER HAS BEEN APPROVED	REQUESTOR

This business rule identifies system alerts that are available and who should receive the alert. New Alert types cannot be created.

Alert and Recipient

BACKORDERED ITEMS HAVE ARRIVED - Work Orders and Checkout Requests - Enter REQUESTOR in the Recipient column to have an alert sent to the requestor when backordered items come in. The requestor who's Issue Ticket Report has been printed will receive the alert.

PARTS HAVE ARRIVED - Work Order - Enter REQUESTOR or PLANNER in the RECIPIENT column to have an alert sent to the requestor or planner of a work order with a direct purchase is received in the Receiving module. The default is REQUESTOR. When this is set to PLANNER the alert is sent to the planner indicated on the work order task, not on the work order.

PO ITEM RECEIVED - Requisition - Enter REQUESTOR in the PO ITEM RECEIVED column to have an alert sent to the requestor identified on the Requisition when the requested PO item is received.

WORK ORDER HAS BEEN APPROVED - Work Order - Enter REQUESTOR in the RECIPIENT column to have an alert sent to the work order requestor when approval has been processed for the work order.

WO FINISH WITH OPEN PO OR REQ - Purchase Order, Requisition - Enter the person who should receive an alert when a Work Order that references an open purchase order or requisition is set to Finished status. The Default setting is to BOTH.

Batch Purge Criteria Rule

Business Rule BATCH PURGE CRITERIA

Rule ID: BATCH PURGE CRITERIA Business Parameter Limit?

Desc: This rule defines criteria for batch purge processing.

Comment: Batch processing. Define rule keys to specify criteria for purging of data in batch jobs.

Batch Processing	Status 1	Status 2	Status 3	Status 4
▲ EVENT QUEUE STATUSES	FAILED	FAILED		
REQUISITION PO STATUSES	CLOSED	CANCELED		
WORK REQUEST WO STATUSES	CLOSED	CANCELED	REJECTED	HISTORY
▼				

Description: Work requests associated to work orders in the statuses entered in the Status 1 - 4 columns are purged. For example, if the value in the Status 1 column is set to CLOSED, the system purges any work requests associated to work orders in CLOSED status.

Define the status values which determine when to delete obsolete data. Records are deleted when batch purge processing runs. Enter the applicable statuses in the Status 1, Status 2, and Status 3 columns for each record type. For example, for work requests, if the value in the Status 1 column is set to CLOSED, the system purges any work requests associated to work orders in CLOSED status.

Batch Processing

EVENT QUEUE STATUSES - Delete event queue entries that are in the statuses identified in the status columns.

REQUISITION PO STATUSES - Delete requisitions associated with purchase orders in the statuses identified in the status columns. Typically, Requisitions are considered unnecessary after the PO has been CLOSED or CANCELED.

WORK REQUEST WO STATUSES - Delete work requests associated to work orders that are in the statuses identified in the status columns. Recommended options for Status 1 - 4 include work orders in CLOSED, CANCELED, HISTORY, or REJECTED status. Although it is possible, it is NOT recommended that you purge work requests associated to work orders in PLANNING, PENDING APPROVAL, APPROVED, ACTIVE or FINISHED status.

STATUS 1, STATUS 2, STATUS 3 - These columns indicate the statuses for the records that are purged. Status 1 is the prime status to be deleted. Status 2 and 3 are other desired statuses.

Batch Purge Parameters Rule

Batch Parameters	Days
ALERTS	1
AUDIT LOG	0
BATCH_MESSAGES	7
EVENT QUEUE	5
REQUISITIONS	9
WORK REQUESTS	0

Description
Alerts are those records generated by the system when a defined event occurs requiring user attention. Alerts may be accessed (per user) via the WorkFlow Agent. Purge processing compares the Alert Date to the current

As system data ages, it often becomes of little or no value to users. Purging old data regularly prevents tables from growing too large and helps maintain a quick system response time when querying those tables.

The Batch Purge Parameters Rule defines, per specific type of data, the age of a record before batch processes purges it. Note that the specific routines called for purging are already defined, purging either a single record at a time or a header record and its associated view, whichever is appropriate.

Batch Parameters and Days

ALERTS - Set the number of days the system should retain Alerts on the home page. Purge processing compares the Alert Date to the current date minus the number of days listed in the DAYS column, and deletes any messages that fall outside of that range.

AUDIT LOG - Set the number of days the system should retain Audit Log entries. Purge processing compares the date that the entry was made to the current date minus the number of days listed in the DAYS column, and deletes any messages that fall outside of that range.

BATCH_MESSAGES - Messages generated by batch processing and are stored as records in the Job Manager module so that you can easily access and review them at any time. Purge processing compares the Batch Message Date to the current date minus the number of days listed in the DAYS column, and deletes any messages that fall outside of that range.

REQUISITIONS - Purge Processing compares the PO Status Date (for status settings in the Batch Purge Criteria business rule) to the current date. When the result is greater than the number of days listed in the DAYS column, the Requisition is deleted from the system.

WORK REQUESTS - Purge Processing compares the Work Order Status Date (for status settings in the Batch Purge Criteria business rule) to the current date. When the result is greater than the number of days listed in the DAYS column, the work request is deleted from the system.

Credit Card Purchases Rule

Business Rule CREDIT CARD PURCHASES

Rule ID: CREDIT_CARD_PURCHASES Business Parameter Limit?

Desc: This rule controls whether or not direct purchase items may be paid for using a credit card.

Comment: To control which document types (such as Purchase Orders) may be charged against a credit card, list the document types in the "DOCUMENT TYPE" column and set the "OPTION STATUS" column to ALLOW or

Document Type	Option Status
PURCHASE ORDER	DISALLOW
REQUISITION	DISALLOW
WORK ORDER	ALLOW

Description: Allows user to charge direct purchases against a credit card.

Control which type of documents are valid for direct purchase items to be paid for using a credit card. Direct Purchase items can be paid for using a credit card number (associated with an Employee record) as the charge number.

Document Type and Option Status

PURCHASE ORDER, REQUISITION, WORK ORDER - Allows or prevents users from charging direct purchases against a credit card. Enter ALLOW to enable charging of direct purchases to credit card numbers or DISALLOW to prevent it for each document type.

PO Aging Rules Rule

Business Rule PO AGING RULES

Rule ID: PO AGING RULES Configuration Parameter Limit?

Desc: This rule dictates how long Purchase Orders are to remain in "Fully Invoiced" status before batch processing resets the status to "Closed".

Comment: Batch processing.

Aging Rule	Days
BATCH_CLOSE	0

Description: This key determines how long a Purchase Order must be INVOICED, FULLY before the system changes the status to CLOSED.

Control the amount of time that Purchase Order records will remain in FULLY INVOICED status, before batch processing sets the PO status to CLOSED.

After a Purchase Order reaches Fully Invoiced status, it remains in this status for the number of days defined in this rule. After the defined number of days, batch processing updates the Purchase Order status to Closed.

Aging Rule and Days

BATCH_CLOSE - the process trigger used by the system to find the Purchase Order Aging value and determine if a PO qualifies to be set to CLOSED status. Simply enter the

number of aging days that the PO is to remain in FULLY INVOICED status in the DAYS column.

PO Report Constants Rule

Business Rule PO REPORT CONSTANTS

Rule ID: **PO REPORT CONSTANTS** Business: **Business** Parameter: **Parameter** Limit?

Desc: This rule defines the "constants" for Purchase Orders and Requisitions. Constants are defined as fields consistently used on each report and may include bill to address; ship to address and company name.

Comment: Enter into the description fields the text you would like to appear on the Purchase Order and Requisition reports.

Address Field		Max Lines
ADDRESS_FOR_BILL_TO	(use desc)	(use 5 lines)
ADDRESS_FOR_SHIP_TO	(use desc)	(use 5 lines)
AUTO_PAY_TEXT		
LABEL_DUTY_TAX	Duty:	
LABEL_FEDERAL_TAX	GST:	
LABEL_STATE_TAX	PST:	
LOWER_LEFT_BOTTOM_BOX	(use desc)	
LOWER_LEFT_TOP_BOX	(use desc)	
STANDARD_EMAIL_BODY_TEXT	(use desc)	
TAX_BOX	(use desc)	(use 9 lines)
YOUR_COMPANY_NAME	(use desc)	(use 1 line)

Description: Synergen Associates, Inc. 2121 North California Blvd., Suite 800 Accounts Payable Department, Walnut Creek, California 94596

Define constants for POs and Requisitions to avoid repetitious data entry on these records. Constants are defined as fields consistently used on each report and may include values such as Bill To Address or Company Name.

Highlight a Rule Key and enter the text that you want to have appear on the Purchase Order and Requisition reports for that parameter in the Description field at the bottom of the screen.

Address Field and Max Lines

ADDRESS_FOR_BILL_TO - Use the description field to enter the address that should be printed on each report. The system first looks at the storeroom setup record for a Bill To Address. If no address is found, the ADDRESS_FOR_BILL_TO address field is used.

ADDRESS_FOR_SHIP_TO - Use the description field to enter the ship to address that should be printed on each report. The system first looks at the storeroom setup record for a Ship To Address. If no address is found, the ADDRESS_FOR_SHIP_TO address field is used.

AUTO_PAY-TEXT - Use the description field to enter the text that should appear on automatic invoices.

LABEL_DUTY_TAX - Use the description field to enter the label for the duty rate. The value entered for the LABEL_DUTY_TAX address field will be used throughout the application as well as on reports. For example, this the label entered here will display on the Design Estimate view in the Work Design module or the Line Item (Detail) on a Purchase Order record. If no value is entered here "Duty" is used as the default label.

LABEL_FEDERAL_TAX - Use the description field to enter the label for the federal tax rate.

LABEL_STATE_TAX - Use the description field to enter the label for the state tax rate.

LOWER_LEFT_BOTTOM_BOX - Use the description field to enter any information that

you want to appear in the large box on the bottom left hand side of the Purchase Order and Requisition Reports. This box can be used as desired. For example, invoicing information could be referenced.

LOWER_LEFT_TOP_BOX - Use the description field to enter any information that you want to appear in the smaller box on the bottom left-hand side of the purchase order and requisition reports. For example, reminders or announcements could be indicated.

STANDARD_EMAIL_BODY_TEXT - Use the description field to enter the text that will appear in the message when you e-mail a Purchase Order to a vendor.

TAX_BOX - Use the description field to enter the text that should appear with Tax information on PO reports.

YOUR_COMPANY_NAME - Use the description field to enter the company name that should appear at the top of the of the Purchase Order and Requisition Reports as well as in the subject line of e-mails with Purchase Orders sent to Vendors.

Max Lines

This column defines the number of lines in the description field that will be retrieved and inserted into the Purchase Order and Requisition Report.

PO Report Status Codes Rule

Business Rule PO REPORT STATUS CODES

Rule ID: PO REPORT STATUS CODES Business Parameter Limit?

Desc: This rule defines the statuses of a Purchase Order that control the printing/e-mailing of the Purchase Order Report.

Comment: A Purchase Order can be printed or e-mailed only if its status is in one of the statuses listed in this business rule with the option value set to 'ALLOW'. A Purchase order is not printed either if its status is

PO Status	Option Status
APPROVED	ALLOW
ISSUED	ALLOW

Description

Define when Purchase Orders can be printed.

A Purchase Order can only be printed when it is in one of the statuses listed in this Business Rule with the option value set to ALLOW.

This rule also controls which PO numbers appear in the Purchase Order Number List of Values on the selection screen for S_RPT053. For example, if the Option Status for PO Status Approved is set to DISALLOW, Purchase Orders in Approved status will not show on the lists of values when you are selecting options for this report.

PO Status and Option Status

Purchase Order statuses include: APPROVED, CANCELED, CLOSED, CREATED, INVOICED, ISSUED, PENDING APPROVAL, and RECEIVED. Select a status then enter either ALLOW or DISALLOW in the Option Status field to determine when a PO in that status can be printed.

Purchasing Options Rule

Option	Status	Values
▲ BOTH EDI/AUTOFAX WHO WINS		EDI
DEFAULT PRINT PO ITEM IND	OFF	
DISPLAY BLANKET RFQ EXP ACTION	ON	
ENFORCE APPROVED VENDOR	ON	
EXPEDITE ITEM DETAILS	ON	
LEAD TIME	ON	BUSINESS
RESTRICT ITEMS BY PO TYPE	OFF	
STORES LOOKAHEAD REQUIRED DATE		PO
TEMPORARY STOCK STOREROOM	ON	TMP

The Purchasing Options Rule defines processing options for the Purchasing subsystem.

Option, Status, and Value

ACCOUNTS REQUIRED ON PENDING - This rule determines when the system checks for valid account splits on purchasing records. When it is set to ON, changing to Pending Approval status triggers the validation. When it is set to OFF the system validates accounts when the record is changed to Approved status. The default setting is “ON”.

BOTH EDI/AUTOFAX WHO WINS - This rule key determines whether EDI or Auto-fax will be used, if both are available methods to transmit purchasing documents.

DEFAULT PRINT PO ITEM IND - This rule key determines the default setting of the Print Line Item indicator when a Purchase Order is copied to a Change Order.

DISPLAY BLANKET RFQ EXP ACTION - When this rule key is set to ON the Export Blkt RFQ to File action is displayed on the Actions list in the Request for Quotes module. This action allows users to export the Blanket RFQ data to an Excel spreadsheet.

ENFORCE APPROVED VENDOR - This line determines if the approved vendor limitation will be enforced for purchasing documents during online and batch processing. When the status is set to ON, if any item on a PO (or other purchasing document) requires an approved vendor, as defined by the procurement level field, then the entire PO requires an approved vendor. The approved vendor requirement will be enforced when the PO is issued. Only users with an Approval Title with the document type AVOVERRIDE have the option of dismissing the requirement.

EXPEDITE ITEM DETAILS - This rule key determines whether or not there are item details for purchase expedite records. When the status is set to ON, the system provides a View to the PO Expediting module in the Purchasing subsystem. This view can be used for tracking partial shipments, and an informational version of the window is also offered as a view of the Purchase Order module in the Purchasing subsystem.

LEAD TIME - The lead time indicates whether the system will calculate a default Promise Date on Purchase Orders created through using batch processing and Blanket Contracts. If the value is set to CALENDAR, all days are included in the calculation of the promise date.

RESTRICT ITEMS BY PO TYPE - The intention of this rule key is to allow or disallow the

mingling of different stock code types on a single purchase order.

Note: Regardless of the rule key setting, any time a stock code is entered on a purchase order line item, the line item type must be “M” (Materials). This rule key only pertains to Purchase Order Type and Stock Item Type.

When the status is set to ON the system enforces restrictions on the combination of stock type and purchase order types that can be included together on purchasing documents. These restrictions are based on the following:

- Direct type stock items - Can only be added to P (purchase), B (blanket contract) and W (work order generated) type purchasing documents
- Inventory or Expense type stock items - Can only be added to S (stores replenishment type) purchasing documents
- This setting does not affect S and W type purchasing documents generated by Batch Processing.

When the status is set to OFF, you can combine stock types (Direct, Inventory, and Expense) and purchase types (B, P, S, V, and W) without these restrictions, however there are general restrictions which apply whether the rule key set to ON or OFF. Please refer to the following table for details:

Purchase Type	Blanket (B)	Purchase (P)	Services (V)	Stores Replenishment (S)	Work Order Generated (W)
Stock Types Allowed by Purchase Type	Expense Inventory Direct	Direct	Direct	Expense Inventory	Direct
Stock Types Not Allowed by Purchase Type	Phantom Consignment	Phantom Consignment Inventory	Phantom Consignment Inventory Expense	Phantom Consignment Direct	Phantom Consignment Inventory Expense
PO Line Types Allowed by Purchase Type	Materials Services Misc.	Materials Services Misc.	Materials Services Misc.	Materials	Materials Services Misc.

STORES LOOKAHEAD REQUIRED DATE - This rule key determines which date is used as the promised date for items on a purchase order. Set the key to PO to use the promise date on the purchase order header for every item. Set the key to PO ITEM to use the promise date from each individual purchase order line item.

TEMPORARY STOCK STOREROOM - If the storeroom is identified and this rule key is set to ON, direct purchase items are allocated to the original purchase order to ensure proper issuance of the material upon receipt. Only Active storerooms with Direct stock type can be chosen from the list of values.

Code Tables

Code Table 7: Location (Length = 10)

Deliver to Location field - Define codes to designate possible delivery locations within your organization. Typical entries include: “North side loading dock” or “Main Warehouse”.

Code Table 23: Unit of Measure (Line Item (Detail) View) (Length = 4)

Unit of Purchase (UOP) and Unit of Issue (UOI) fields - Define units codes. These fields are used by the system to maintain quantities as parts are issued and new parts are received. You may, for instance, issue in units of each ('EA') but order in units of boxes ('BOX') where one box would contain 10 individual items. Code Table 23 enables you to define the different Units of Purchase and Units of Issue.

Code Table 26: End Use Code (Buyer Data View) (Length = 2)

End Use Code field - Define codes to identify where items for the requisition are to be used in the plant. Examples include: 'D' for Specific Department Usage, 'P' Plant Wide Usage, etc.

Code Table 43: FOB (Buyer Data View) (Length = 20)

F.O.B. (Free On Board) designates from which point the Buyer pays for the delivery charges. This code table is typically populated with Vendor and Buyer locations.

Code Table 150: Confirmation Types (Buyer Data View) (Length = 10)

Confirmation Type field - Define codes to indicate how the vendor was contacted for confirmation. Typical entries include phone, fax, e-mail.

Code Table 154: Expediting Item Status (Expedite View, Expedite Items Detail) (Length = 15)

Status field - This code table relates to the status of the expedited items. The code table is attached to the Status Code field and some examples of data are: Backorder, Ready, and Shipped.

Code Table 159: Federal Tax Codes (Buyer Data View) (Length = 1)

Federal field - The code can only be one character long and the Description should contain the percentage rate in the first six characters of the field.

Code Table 160: State Tax Codes (Buyer Data View) (Length = 1)

State field - The code can only be one character and the Description should contain the percentage rate in the first six characters of the field.

Code Table 161: Duty Codes (Buyer Data View) (Length = 1)

Duty field - The code can only be one character long and the Description should contain the percentage rate in the first six characters of the field.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Change PO Auto Pay Indicator

Grants the ability to change a vendor's auto pay flag on Purchase Order records.

Copy PO from PO

Grants the ability to copy Purchase Orders using the Copy Record action.

Transfer Canceled PO Items

Grants the ability to transfer canceled Purchase Order items.

Resend Approval Request

Grants the ability to resend an Approval Request using the Resend Approval Request action in the Purchase Order module.

Batch Processes

Purge Requisitions - sdbp_purge_requisitions;

Enable or disable a batch job to purge Requisitions in PO Created status where the PO is in a certain status. The status and age are defined in the Batch Purge Parameters and Batch Purge Criteria Business Rules.

Vendor Performance - sdbp_vendor_performance;

Supports the gathering of Vendor Performance statistics. This procedure performs the following:

- Identifies the processing parameters for the Current Rating Period for Active Vendors.
- Updates Quality Performance data based on changes since the last batch run.
- Updates Delivery Performance data for new transactions.
- Updates Quality Performance data for new transactions.

Check Received PO Item - sdbp_chk_issd_po_item;

Sends an alert to the PO Item Requestor if the PO is fully received. This procedure looks for all issued PO records. For each PO line item with the field Receipts-Fully Received = Y, an Alert will be sent to the Requestor via the home page inbox. If the Requestor is invalid or null, a message will go to the job manager. The field Sent Alert Indicator on the PO Item is set to Y after an Alert/Job Log Message is sent. The Alert will only be sent once.

PO Closeout - sdbp_po_closeout;

Reviews Purchase Orders, setting the header status to Received, Fully, Invoice, Fully, or Closed as appropriate. Before a Purchase Order is set to Closed status, it must remain in Invoiced, Fully status for the number of days defined in the PO Aging Business Rule.

Charts

S_CHT133 - PO By Buyer - Total Amount

The Total Amount of Purchase Orders for the current year and the previous year. The data can be filtered by Plant and Buyer. There are also other filtering options such as Vendor Code, available in the Chart Field List.

S_CHT134 - PO By Buyer - Count of POs

The count of Purchase Orders for the current year and the previous year. The data can be filtered by Plant and Buyer. Other filtering options, such as Vendor Code, are available in the Chart Field List.

S_CHT135 - PO By Vendor - Total Amount

Shows the Total Amount of Purchase Orders for the current year and the previous year. The data can be filtered further by Plant and Vendor Name. Other filtering options, such as Buyer, PO Type and PO Status, are available in the Chart Field List.

S_CHT1136 - PO By Vendor - Count of POs

A count of Purchase Orders for the current year and previous years. The data can be filtered further by Plant and Vendor Name. Other filtering options, such as Buyer, PO Type and PO Status, are available in the Chart Field List.

Metrics

S_MTRC2 - Internal Time to Issue PO - sdbp_metric_int_time_to_issue

This metric is to provide an average lead-time (in days) for Purchase Order creation (approved Requisition to issued PO). It provides a means to monitor and improve the

internal time required to issue a PO for an approved Requisition.

S_MTRC3 - Total Lead Time - sdbp_metric_total_lead_time

This metric is to provide an average lead-time (in days) for the entire purchasing process (approved Requisition to first PO receipt). It provides a means to monitor and improve the total time (internal and external) required to receive items for an approved Requisition.

S_MTRC4 - External Time to Receive Parts - sdbp_metric_ext_time_rec_part

This metric is to provide an average lead-time (in days) for external purchasing. It provides a means to monitor and improve the external lead-time for Purchase Orders.

Reports

S_RPT105 - Accruals By Account Report

Displays accrued account totals for individual POs.

S_RPT214 - Contract PO Activity Report

Summarizes Purchase Order activity against Blanket Contracts.

S_RPT107 - Delivery Receiving Report

Summarizes Purchase Order and Receiving information for selected Receiving sessions.

S_RPT027 - Delivery Ticket Report

Displays a Delivery Ticket that can be left with the Requestor when PO line items are delivered.

S_RPT212 - Open Purchase Orders Detail Report

Displays a detailed review of Purchase Orders that have not yet been completed.

S_RPT211 - Open Purchase Orders Summary Report

Displays a Summary of Purchase Orders that have not yet been completed.

S_RPT024 - Purchase Order Accruals (Unpaid Receipts) Report

Lists Purchase Orders with items that are not fully invoiced.

S_RPT062 - Purchase Order Accruals (Unpaid POs) Report

Provides a summary of the accruals based on open purchase orders.

S_RPT204 - Purchase Order Expensing Account Detail Report

Lists Purchase Orders by Expense Code.

S_RPT202 - Purchase Order Inventory Item Cost Report

Displays Cost Summaries of all Purchase Orders made for "stocked" items to compare current purchase price with average unit price and calculate the price variance.

S_RPT203 - Purchase Order Listing Report - Grouped by PO Number

Lists Purchase Orders grouped by Purchase Order numbers then Vendor then stock code.

S_RPT201 - Purchase Order Listing Report - Grouped by Vendor Code

Displays a summary of all Purchase Orders Grouped by Vendor Code.

S_RPT029 - Purchase Order Over Received Report

Lists Purchase Orders where the quantity received is greater than the quantity ordered.

S_RPT208 - Purchase Order Report - Department Copy

This is a copy of the Purchase Order that was sent to the Vendor.

S_RPT209 - Purchase Order Report - Finance Copy

This is a copy of the Purchase Order that was sent to the Vendor formatted to be sent to the accounting department.

S_RPT207 - Purchase Order Report - Vendor Copy

The Purchase Order that is sent to Vendor's when orders are made.

S_RPT200 - Purchase Order Vendor Report

Displays a Vendor summary of all Purchase Orders within a Date Range.

S_RPT053 - Purchase Order Report

Shows POs that need to be filled by a specific Vendor. Only Document Attachments and Document type Procedures will be printed on the report. The "Print?" check box must be checked.

Please see refer to the PO Report Constants and PO Report Status Codes Business Rules for more information on the Purchase Order Report.

S_RPT112 - Purchase Order Report with Standard Notes and Attachments

Lists outstanding Purchase Orders that need to be filled. Please refer to the PO Report Constants and PO Report Status Codes Business Rules for More information regarding this report.

S_RPT023 - Purchase Orders Not Yet Received Report

Lists Purchase Orders where the quantity received is less than the quantity ordered.

S_RPT010 - Purchase Orders with Returns Report

Lists Purchase Orders with items returned to the Vendor. The return may be for Replacement or Credit.

S_RPT063 - Ready for Payment Report

Provides a listing of Purchase Orders that are ready for payment.

S_RPT025 - Receiving Report

Lists summary Purchase Order and Receiving information for selected Receiving sessions.

S_RPT216 - Receiving Report

Summarizes receiving records by Purchase Order number detailing items received, by whom, receipt date, and other applicable information.

S_RPT037 - Receiving Worksheet Report

Lists items to be received as well as any existing Receiving information.

Change Order Module

Fields

Approval Route Field

Designate approvers for Change Orders in the Approval Limits module of the Administration subsystem under Approvals and Routes.

Business Rules

C.O. Auto Approve Percentage Rule

The screenshot shows a configuration window titled "Business Rule C.O. AUTO APPROVE PERCENTAGE". It contains the following fields and controls:

- Rule ID:** C.O. AUTO APPROVE PERCENTAGE
- Business:** Business (dropdown menu)
- Parameter:** Parameter (dropdown menu)
- Limit?:**
- Desc:** This rule dictates the maximum percentage price difference allowed for automatic approval. To exceed the price percentage requires the user to enter approvals to approve the Change Order.
- Comment:** (Empty text area)
- Table:** A table with two columns: "Auto Approve Percentage" and "Max Percent". The first row contains "CO_AUTO_APPROVE_PERCENTAGE" and "10".
- Description:** The maximum price difference percentage allowed (in whole percentages) for auto-approval.

Auto Approve Percentage	Max Percent
CO_AUTO_APPROVE_PERCENTAGE	10

Set the percentage over the Purchase Order value at which the system will automatically approve a Change Order. When a Change Order is modified, the new Change Order total value may be different than the originating Purchase Order value. If the price difference is less than or equal to a defined percentage, the system can automatically approve the Change Order when a user sets the Change Order status to Pending Approval.

To Search for this rule on the Search Options screen make sure to include the periods in between C.O.

Auto Approve Percentage and Max Percent

CO_AUTO_APPROVE_PERCENTAGE - Enter into the MAX PERCENT column the maximum price difference allowed (as a whole number percentage) for auto-approval of Change Orders. If the new Change Order price difference exceeds this percent, users must manually enter approval information to approve the Change Order. If you do not want to allow automatic approval at any value set the Max Percent to 0%.

Purchasing Options Rule

Option	Status	Values
▲ BOTH EDI/AUTOFAX WHO WINS		EDI
DEFAULT PRINT PO ITEM IND	OFF	
DISPLAY BLANKET RFQ EXP ACTION	ON	
ENFORCE APPROVED VENDOR	ON	
EXPEDITE ITEM DETAILS	ON	
LEAD TIME	ON	BUSINESS
RESTRICT ITEMS BY PO TYPE	OFF	
STORES LOOKAHEAD REQUIRED DATE		PO
TEMPORARY STOCK STOREROOM	ON	TMP

Set purchasing options.

For descriptions of the remaining rule keys please refer to the Purchase Order module configuration.

Option, Status, and Value

ACCOUNTS REQUIRED ON PENDING - This rule determines when the system checks for valid account splits on purchasing records. When it is set to ON, changing to Pending Approval status triggers the validation. When it is set to OFF the system validates accounts when the record is changed to Approved status. The default setting is "ON".

STORES LOOKAHEAD REQUIRED DATE - This rule key determines which date is used as the promised date for items on a purchase order. Set the key to PO to use the promise date on the purchase order header for every item. Set the key to PO ITEM to use the promise date from each individual purchase order line item.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Resend Approval Request

Grants the ability to resend an Approval Request using the Resend Approval Request Action in the Change Order module.

Blanket Contract Module

Fields

Sequence No.: Blanket Contract No.

The record number is comprised of a unique ID (Ex. "B000127"). Purchasing record numbers are typically set to be system generated.

TABLE NAME - SA_BLANKET_CONTRACT - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Business Rules

Attachment Drive Mapping Rule

The screenshot shows a configuration window titled "Business Rule ATTACHMENT DRIVE MAPPING". It contains the following fields and controls:

- Rule ID:** ATTACHMENT DRIVE MAPPING
- Business:** Business
- List:** List
- Limit?:**
- Desc:** This rule is for Attachment drive mapping.
- Comment:** (Empty text area)
- Drive Map:** A list of drive letters: G, O, P, V, W.
- Machine Name:** A list of machine names: W10.138.131.95\attac, \\walnutcreek\dept, W10.138.131.97\attac, W10.138.131.105\use, \\ball\synergen\qa171
- Description:** Rome Attachments.

.Use this rule to map attachment files for the Blanket Contract and Purchase Order modules.

Enter a drive and machine that it should be mapped to in the appropriate columns. Attachments stored on these drives and attached to Blanket Contract or Purchase Order records will be converted to the UNC path and attached to any e-mail sent from the record where the E-Mail Purchase Order action is selected and the Print indicator is checked.

Multiple Active Contracts Rule

Active Contract Status	Option
MULTIPLE REVISIONS	ON

Determine whether or not a Blanket Contract can have multiple revisions active at the same time.

Default processing only allows one revision to be active at a time. If this rule is set to OFF and a user tries to make an additional revision active, a message will appear alerting the user that all other revisions of the Blanket Contract will be set to created status.

Active Contract Status and Option

Enter ON or OFF in the OPTION column to enable or disable the ability of having a Blanket Contract with more than one active revision. The default is OFF.

Blanket Contract Processing Rule

Blanket Contract Parameters	Options	Values
ACTIVATE ON INITIATION DATE	ON	
BLANKET CONTRACT AMOUNT	ON	150
BLANKET CONTRACT PERCENT	ON	15
CLOSE ON EXPIRATION DATE	ON	
CONTINUE PO NEXT ACTION	ALLOW	
CONTINUE REQ NEXT ACTION	ALLOW	
ENFORCE 'B' TYPE	ON	
EXPIRE DATE TOLERANCE	ON	5
STANDARD_EMAIL_BODY_TEXT	(use desc)	
USE MASTER ACCESS LIST	ON	

Define processing options on Blanket Contracts.

Blanket Contract Parameters, Options, and Values

ACTIVATE ON INITIATION DATE - If this option is set to ON, batch processing will Auto-Activate Blanket Contracts when the initiation date has been reached.

BLANKET CONTRACT AMOUNT - If this option is set to On, the User-defined Dollar Amount entered in the Values field represents the Amount prior to reaching the Blanket Contract Limit Amount that will invoke the allow to continue processing.

BLANKET CONTRACT PERCENT - If this option is set to On, the User-defined Percentage Value entered in the Values field represents the Percentage of a Dollar Value prior to reaching the Blanket Contract Limit Amount that will invoke the allow to continue processing.

CONTINUE PO NEXT ACTION - This determines if the processing of a Purchase Order will be allowed to continue after Warning Message(s) displays that any point of Blanket Contract Validation fails.

CONTINUE REQ. NEXT ACTION - This determines if the processing of a Requisition will be allowed to continue after Warning Message(s) displays that any point of Blanket Contract Validation fails.

ENFORCE "B" TYPE - If this option is set to ON the Requisition Type in Requisition module will enforce 'B' type when referencing to a Blanket Contract.

EXPIRE DATE TOLERANCE- If this option is set to On, the User-defined Number entered in the Values field will represent the Number of Days prior to reaching the Blanket Contract Expiration Date that will invoke the allow to continue processing.

STANDARD E-MAIL BODY TEXT - Enter the standard text that should appear on e-mails that are sent to vendors by the system.

USE MASTER ACCESS LIST- If this option set to ON, the Users listed in the BLANKET CONTRACT ACCESS LIST Business Rule will be authorized to Approve and Issue releases against Blanket Contracts that have the USE MASTER ACCESS LIST indicator is checked.

Blanket Contract Access List Rule

Business Rule BLANKET CONTRACT ACCESS LIST

Rule ID: Business Limit?

Desc: This rule identifies the Users that have authority to release against Blanket Contracts that have the USE MASTER ACCESS LIST indicator set (requires the USE MASTER ACCESS LIST rule key in the BLANKET

Comment:

User Name	User Limit	Storeroom
BRANAVEN	100000	BYB
BROWN	100000	IB1
RAY	10000	RAY
RBEELER	100000	RB1
RVEKSLER	100000	RVM
WILLY	10000	OKC

Description:

Define Users authorized to use Blanket Contracts when the User Master Access List indicator is checked.

User Name, User Limit, and Storeroom

The Users listed have authority to release against Blanket Contracts that have the USE MASTER ACCESS LIST indicator set, and when the USE MASTER ACCESS LIST key in the BLANKET CONTRACT PROCESSING rule is ON. The User Limit represents the maximum dollar amount that the user can charge against a contract for a single Purchase Order. The Storeroom field is for informational purposes only and indicates the storeroom that the user normally works from.

Purchasing Options Rule

Option	Status	Values
▲ BOTH EDI/AUTOFAX WHO WINS		EDI
DEFAULT PRINT PO ITEM IND	OFF	
DISPLAY BLANKET RFQ EXP ACTION	ON	
ENFORCE APPROVED VENDOR	ON	
EXPEDITE ITEM DETAILS	ON	
LEAD TIME	ON	BUSINESS
RESTRICT ITEMS BY PO TYPE	OFF	
STORES LOOKAHEAD REQUIRED DATE		PO
TEMPORARY STOCK STOREROOM	ON	TMP

The Purchasing Options Rule defines processing options for the Purchasing subsystem.

Option, Status, and Value

ACCOUNTS REQUIRED ON PENDING - This rule determines when the system checks for valid account splits on purchasing records. When it is set to ON, changing to Pending Approval status triggers the validation. When it is set to OFF the system validates accounts when the record is changed to Approved status. The default setting is "ON".

BOTH EDI/AUTOFAX WHO WINS - This rule key determines whether EDI or Auto-fax will be used, if both are available methods to transmit purchasing documents.

DEFAULT PRINT PO ITEM IND - This rule key determines the default setting of the Print Line Item indicator when a Purchase Order is copied to a Change Order.

DISPLAY BLANKET RFQ EXP ACTION - When this rule key is set to ON the Export Blkt RFQ to File action is displayed on the Actions list in the Request for Quotes module. This action allows users to export the Blanket RFQ data to an Excel spreadsheet.

ENFORCE APPROVED VENDOR - This line determines if the approved vendor limitation will be enforced for purchasing documents during online and batch processing. When the status is set to ON, if any item on a PO (or other purchasing document) requires an approved vendor, as defined by the procurement level field, then the entire PO requires an approved vendor. The approved vendor requirement will be enforced when the PO is issued. Only users with an Approval Title with the document type AVOVERRIDE have the option of dismissing the requirement.

EXPEDITE ITEM DETAILS - This rule key determines whether or not there are item details for purchase expedite records. When the status is set to ON, the system provides a View to the PO Expediting module in the Purchasing subsystem. This view can be used for tracking partial shipments, and an informational version of the window is also offered as a view of the Purchase Order module in the Purchasing subsystem.

LEAD TIME - The lead time indicates whether the system will calculate a default Promise Date on Purchase Orders created through using batch processing and Blanket Contracts. If the value is set to CALENDAR, all days are included in the calculation of the promise date.

RESTRICT ITEMS BY PO TYPE - The intention of this rule key is to allow or disallow the

mingling of different stock code types on a single purchase order.

Note: Regardless of the rule key setting, any time a stock code is entered on a purchase order line item, the line item type must be “M” (Materials). This rule key only pertains to Purchase Order Type and Stock Item Type.

When the status is set to ON the system enforces restrictions on the combination of stock type and purchase order types that can be included together on purchasing documents. These restrictions are based on the following:

- Direct type stock items - Can only be added to P (purchase), B (blanket contract) and W (work order generated) type purchasing documents
- Inventory or Expense type stock items - Can only be added to S (stores replenishment type) purchasing documents
- This setting does not affect S and W type purchasing documents generated by Batch Processing.

When the status is set to OFF, you can combine stock types (Direct, Inventory, and Expense) and purchase types (B, P, S, V, and W) without these restrictions, however there are general restrictions which apply whether the rule key set to ON or OFF. Please refer to the following table for details:

Purchase Type	Blanket (B)	Purchase (P)	Services (V)	Stores Replenishment (S)	Work Order Generated (W)
Stock Types Allowed by Purchase Type	Expense Inventory Direct	Direct	Direct	Expense Inventory	Direct
Stock Types Not Allowed by Purchase Type	Phantom Consignment	Phantom Consignment Inventory	Phantom Consignment Inventory Expense	Phantom Consignment Direct	Phantom Consignment Inventory Expense
PO Line Types Allowed by Purchase Type	Materials Services Misc.	Materials Services Misc.	Materials Services Misc.	Materials	Materials Services Misc.

STORES LOOKAHEAD REQUIRED DATE - This rule key determines which date is used as the promised date for items on a purchase order. Set the key to PO to use the promise date on the purchase order header for every item. Set the key to PO ITEM to use the promise date from each individual purchase order line item.

TEMPORARY STOCK STOREROOM - If the storeroom is identified and this rule key is set to ON, direct purchase items are allocated to the original purchase order to ensure proper issuance of the material upon receipt. Only Active storerooms with Direct stock type can be chosen from the list of values.

Code Tables

Code Table 35: Blanket Contract Category Codes

Category field - Define categories to classify Contract records. The two system values of DIRECT and INVENTORY cannot be removed or changed; but additional category codes can be defined. This is a system code table.

Copy Record

BLNKTCON - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

CREATE BLANKET CONTRACT REVS

Grants access to the Create Revision action in the Blanket Contract module.

CREATE BLNKET CONTRACT REV HIST

Grants access to the Create Revision with History action in the Blanket Contract module.

DUPLICATE BLANKET TO PO

Grants access to the Copy Record action in the Blanket Contract to PO module.

Batch Processes

Auto Activate Blankets - sdbp_blanket_services.auto_activate;

Sets Blanket Contracts to Active status on the Initiation Date indicated on the Blanket Contracts.

Auto Close Blankets - sdbp_blanket_services.auto_close;

Closes Active Blanket Contracts on the Expiration Date or the Extended Date indicated on the Blanket Contracts.

Reports

S_RPT206 - Blanket Contract Report

Summarizes Blanket Contracts showing stock codes with manufacturers, part numbers, prices, and other important information.

Request for Quotes Module

Fields

Sequence No.: Request for Quotes

The record number is comprised of a unique ID (Ex. "02000033"). Purchasing record numbers are typically set to be system generated.

TABLE NAME - SA_QUOTE - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Next Approver Field

Designate approvers for Requests for Quotes in the Approval Limits module of the Administration subsystem under Approvals and Routes.

Business Rules

Default Directories Rule

The screenshot shows a configuration window titled "Business Rule DEFAULT DIRECTORIES". It contains the following fields and table:

- Rule ID: DEFAULT DIRECTORIES
- Business: Business
- Parameter: Parameter
- Limit?:
- Desc: This rule defines default directories
- Comment: This rule is used when performing client-side operations
- Table with columns: Directory, Path
- Description: This is the default directory to put barcode label files into

Directory	Path
BAR CODE LABEL DROP DIRECTORY	c:\of
INSTALLED DIRECTORY	c:\sy
OPER DATA EXPORT DIRECTORY	c:\er
OPER DATA IMPORT DIRECTORY	c:\er
RFQ EXPORT DIRECTORY	c:\er
RFQ IMPORT DIRECTORY	c:\er

The Default Directories rule defines default locations for files outside of the Oracle Utilities Work and Asset Management database and is used for saving or calling files from the client computer. Individual users can establish settings in their individual User Profile record in the Administration subsystem that will supersede these business rule settings.

The Default Directories rule should not be confused with the similar Default File Locations rule, which is used to define specific file names and the paths leading to them.

Directory

BAR CODE LABEL DROP DIRECTORY - default directory to put bar code label files into.

INSTALLED DIRECTORY - directory where the application files are located.

OPER DATA EXPORT DIRECTORY - default directory for exporting Operational Data files.

OPER DATA IMPORT DIRECTORY - default directory for importing Operational Data files.

RFQ EXPORT DIRECTORY - default directory for exporting RFQ files.

RFQ IMPORT DIRECTORY - default directory for importing RFQ files.\

COMPONENT UPLOAD DIRECTORY - directory where files are stored when they are uploaded to support receiving multiple trackable components.

Path

This is the hard drive storage location for the corresponding file.

Vendor Performance Ranges Rule

Range	Lower%	Higher%	Multiplier
RANGE1	0	50	1.1
RANGE2	50	75	1.05
RANGE3	75	100	1.0

The Vendor Performance Ranges Rule is used to specify the “Best Price Multiplier” for given performance ranges. You can establish as many ranges as you want, but you must be sure that the ranges do not overlap. Ranges should be whole numbers only.

Range

Ranges should be named Range1, Range2, Range3, up to the total number of ranges that you want to define.

Lower %

Enter the lower percentage (>/=) value for the Total Vendor Performance for the range. Do not use decimal values.

Higher %

Enter the higher (<) percentage value for the Total Vendor Performance for the range. Do not use decimal values. Since this is a ‘less than’ value, you must use 101% to include vendor performance rating of 100% within the range.

Multiplier

Enter the multiplier value for the range. You can define multiplier values to increase bids

from vendors with lower vendor performance ranges. This concept is discussed in more depth in the User Guide section titled Using Ratings in the RFQ Process.

RangeLower %Higher %Multiplier

Range1911011.0

Range285901.05

Range30841.1

Note: This rule is also configured under the Vendor module, however it affects the analysis of the RFQ module.

Code Tables

Code Table 17: Issue Methods (Vendor (Detail) View)

Issue Method field - Define codes to identify ways in which Requests for Quotes can be issued to vendors. Some examples of data are: Priority Mail, Fax, US Mail, Spreadsheet File.

Copy Record

RFQ - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Add Vendor After RFQ Issued

Grants the ability to add vendors to an RFQ after the record has been set to Issued status.

Award RFQ

Grants the ability to award Requests for Quotes to vendors.

Export RFQ

Grants the ability to export Requests for Quotes to another type of file (usually a spreadsheet).

Import RFQ

Grants the ability to import Requests for Quotes from another type of file (usually a spreadsheet).

Issue RFQ

Grants the ability to issue Requests for Quotes to vendors.

Reports

S_RPT093 - Request for Quotes Report

Lists RFQs that are ready to be sent to Vendors.

Invoicing Module

Fields

Approval Route Field

Designate approvers for work requests in the Approval Limit module under Approvals and Routes in the Administration subsystem.

Business Rules

Federal Tax Rebate Rule

The screenshot shows a configuration window titled "Business Rule FEDERAL TAX REBATE". It contains the following fields and controls:

- Rule ID:** FEDERAL TAX REBATE
- Business:** Business (dropdown menu)
- List:** List (dropdown menu)
- Limit?:** Limit?
- Desc:** This business rule will associate a rebate rate and an account/expense code offset for each tax code in code table 159.
- Comment:** The rebate amount is posted as an IN transaction to the Account Log and is accrued to the account listed in the business rule. There is no effect on the average unit price in Synergen.
- Table:** A table with columns: Tax Code, Rebate Rate, Expense Code, and Account Number (partially visible as "Ac").
- Description:** A text area for additional notes.

Associate rebate rates and account/expense code offsets for each tax code in Code Table 159. The functionality used to prorate associated costs in invoicing uses this rule. If the check box on the Invoice Prorate view of the Invoicing module is not selected, the account/expense code listed in this rule is used to accrue the taxes. The rebate rate reflects how much of the tax to accrue, i.e., 100 = all taxes, etc.

This rule can also be used to pass accruals to defined interfaces.

Tax Code, Rebate Rate, Expense Codes, and Account Number

Enter the Tax Code in the Tax Code field, then enter the Rebate Rate, Expense Code, and Account number that you want to automatically associate with that Tax Code. The rebate amount is posted as an IN transaction to the Account Log and is accrued to the account specified.

Invoice Setup Criteria Rule

Business Rule INVOICE SETUP CRITERIA

Rule ID: Business Limit?

Desc:

Comment:

Rule	Option
ALLOW ACCOUNT UPDATE	YES
ALLOW MISMATCHED INVOICING	YES
ALLOW NONTAX PRORATING	YES
DISPLAY ACCRUAL TAX TOTAL	YES
ERS NEXT APPROVER	RVM001
INVOICE TOTAL COMPARE	NO
NEGATIVE DISCOUNT	NO
POST INVOICE	APPROVED
PRORATE	POSTED
SEND ALL BATCHES TO A/P	NO
SEND BATCH TO A/P	NO

Description:

Define how invoice processing will be handled. If this rule is missing or an option is not listed, the default is “NO”.

Rule and Option

ALLOW ACCOUNT UPDATE - If this rule key is set to YES users can override and change the Account for Inventory and Expense type stock codes on Invoice Line Items. User's responsibility profile must also contain the function, INVOICE ACCOUNT OVERRIDE.

ALLOW MISMATCHED INVOICING - If this option is set to YES it will allow an Invoice that does not match the Purchase Order to be recorded in the system. The system automatically puts such records into Pending Resolution status. After the mismatch has been resolved, batch processing changes the status to Approved.

ALLOW MULTIPLE POS - When this option is set to ON, you can record more than one purchase order per invoice. The system provides a Change PO button on the Matching to PO views and a Start Again option on the Quick Invoice Wizard where items from additional purchase order(s) can be recorded.

ALLOW NONTAX PRORATING - This option defines whether or not prorating to non-taxed line items is allowed or disallowed.

AVERAGE UNIT PRICE CALCULATION - Defines how the system calculates Average Unit Price (AUP) for a storeroom when the difference between the total amount of an invoiced item is greater than the total amount on the original purchase order item. If the rule is set to OFF, the entire difference is applied evenly among the Storeroom Item On Hand Quantity. If the rule is set to ON, the difference per item is applied.

For example: Assume a brand new storeroom item. PO Item ordered and received for 10 items at \$1 each. Stock Checkout of 8 items, thus On Hand Quantity is 2. Then invoiced at \$2 for all 10 items.

If the rule is set to OFF, the AUP will be \$6.00 (\$1 + Difference divided by On Hand Quantity).

If the rule is set to ON, the AUP will be \$2.00. (\$1 + difference per item).

COPY PO ATTACHMENTS - When this option is set to YES, all existing attachments associated to the Purchase Order header are copied to the new Invoice record. Also any attachments associated to the Purchase Order line item are copied to the new invoice during the Matching to PO process. The default setting is NO.

DISPLAY ACCRUAL TAX TOTAL - Set this option to YES to display the accrued tax total on the invoice header.

ERS NEXT APPROVER - Identifies the next approver for Auto Invoices that have received more items than were ordered.

INVOICE TOTAL COMPARE - Set this option to 'YES' to display a warning when the manual invoice total field and the invoice total amount fields do not match. The warning message be displays when the user attempts to change status to Pending Approval.

NEGATIVE DISCOUNT - Set this option to YES to allow a negative number to be entered in the Discount Rate field on the invoice header. Do this if you want to markup (increase) the item total by the percentage entered.

OVERRIDE DISCOUNT AMOUNT - If this option is set to YES, the Invoice Discount Amount can be manually updated with a new value when the Invoice has an Item Total Amount. When the Invoice Discount Amount is manually updated the Invoice Discount Rate is recalculated appropriately. When the option is set to NO, the Invoice Discount Amount is calculated based on the Discount Rate and cannot be updated manually.

POST INVOICE - This option determines when invoices are posted throughout the system.

If Post Invoice is set to Approved (Default), the system posts invoices when invoices are in Approved status.

If Post Invoice is set to Sent to A/P, the system posts invoices when the invoice status is set to Approved and the Sent to A/P indicator is set to 'Y'.

If Post Issue is set to Paid, the system posts invoices when the invoice status is set to Approved and the Paid Indicator is set to 'Y'.

PRORATE - This option determines when the prorating procedure is executed.

If this option is set to APPROVED, the prorate procedure will be executed when the Invoice status is set to Approved. The user will not be allowed to set the status of the Invoice record from APPROVED back to CREATED.

If this option is set to POSTED, the prorate procedure will be called during batch processing when the Invoice is set to Posted. Status changes from APPROVED back to CREATED are allowed with this setting.

SEND ALL BATCHES TO A/P - Set this option to YES to display the Send All Batches to A/P action in the Invoice Batch module.

SEND BATCH TO A/P - Set this option to YES to display the Send Batch to A/P action in the Invoice Batch module.

SHOW ALL PO LINES IN MATCHING - This option only affects invoice processing when the ALLOW MISMATCHED INVOICING rule key is set to NO. If SHOW ALL PO LINES IN MATCHING is set to YES then all purchase order line items with an "M" type are displayed in the Matching to PO views even if they have been previously matched. This rule option has no impact on "S" or "X" type line items.

If the ALLOW MISMATCHED INVOICING rule key is set to YES then all PO items are displayed in the Matching to PO views even if they have been previously matched regardless of the setting on the SHOW ALL PO LINES IN MATCHING rule key.

Invoice Prorate Defaults Rule

Business Rule INVOICE PRORATE DEFAULTS

Rule ID: INVOICE PRORATE DEFAULTS Business Parameter Limit?

Desc: This rule defines what items may be prorated on an Invoice. If this rule is missing or an option is not listed, the default is to not allow prorating.

Comment: The prorate options are defined in the first column; the option status in the second column. If this rule is missing or an option is not listed, the default is "NO" for prorating that item. The "Tax to Vendor", "PR to NonTax", "Accr Account", and "Expense Code" are defined in the remaining columns.

Prorate Option	Option Status	Tax to Vendor	PR to NonTax	Accr Account	Expense Code
DISCOUNT	YES				
DUTY	YES	NO	NO		
EXTRA	NO				
FEDERAL TAX	YES	NO	NO		
FREIGHT	NO				
STATE TAX	YES	NO	NO		

Description:

Define which costs can be prorated on an Invoice. This rule also controls tax accruals, providing you the ability to pay or not pay taxes to the vendor.

If this rule is missing or an option is not listed, the default is to NOT allow prorating.

The types of expenses that can be entered include DISCOUNT, DUTY TAX, EXTRA COSTS, FEDERAL TAX, FREIGHT CHARGES, and STATE TAX. Enter YES or NO in the Option Status column to allow or disallow the option to prorate the type of charge on an Invoice.

Tax to Vendor

Indicates whether taxes are handled. If YES is entered in this column then taxes are paid to the vendor. If NO is entered in this column, taxes are not paid to the vendor but are accrued, and posted to the Account Log. If SPLIT is entered into this column, then taxes are split between the vendor and the accrual account. If this column is blank, the default is NO.

PR to NonTax

Indicates whether or not taxes are prorated to nontaxed line items. (YES/NO)


Accr Account

Indicates the account to be used for tax accrual amounts. (YES/NO)

Accr Expense

Indicates the Expense Code to be used for tax accrual amounts. (YES/NO)

Invoice Tolerances Rule



Invoice Matching	Tolerance
DOLLAR	100
LOW_DOLLAR	3
LOW_PERCENT	10
LOW_RESULT	WARNING
PERCENT	50
RESULT	WARNING

Set both dollar and percent tolerance values for invoice matching processing. Also determine whether the system displays a warning, or prevents the user from continuing if tolerance values are surpassed.

Invoice Matching and Tolerance

DOLLAR - Enter the maximum allowed whole dollar difference between the Purchase Order Line Item value and the Invoice Line Item value.

LOW DOLLAR - Enter the minimum allowed whole dollar difference between the Purchase Order Line Item value and the Invoice Line Item value.

PERCENT - Enter the maximum allowed whole percent difference between the Purchase Order Line Item value and the Invoice Line Item value.

LOW PERCENT - Enter the minimum allowed whole percent difference between the Purchase Order Line Item value and the Invoice Line Item value.

RESULT - Enter how the system should respond when the value entered is more than allowed. Enter **WARNING** to display a warning message, or **STOP** to prevent the user from continuing.

LOW RESULT - Enter how the system should respond when the value entered is less than allowed. Enter **WARNING** to display a warning message, or **STOP** to prevent the user from continuing.

Payment Terms Rule

Business Rule PAYMENT TERMS

Rule ID: Business Limit?

Desc: This rule defines the payment terms and the number of days for payment.

Comment: Terms Code:
You enter into the "TERMS CODE" column the codes to define your payment terms.

Terms Code	Description	Days	Fixed Date	Dis
10	NET 10/2%	10		2
20	NET 15/5%	15		10
30	AT INVOICE RECEIPT	0		

Description:

Define payment terms and the number of days before payment is due per term.

Terms Code and Description

Enter the codes to define your payment terms, and define the code in the Description column.

Days

Enter the number of days that the system should use to calculate the invoice due date based on the vendor date entered on the invoice.

Fixed Date

If a vendor has arranged for an invoice due date to be the same each month, enter the day into the this column. For example, if 20 is entered in this column, the due date would be the 20th of every month.

Discount %

Enter any discount that might be given for using a certain payment term.

Purchasing Options Rule

Option	Status	Values
▲ BOTH EDI/AUTOFAX WHO WINS		EDI
DEFAULT PRINT PO ITEM IND	OFF	
DISPLAY BLANKET RFQ EXP ACTION	ON	
ENFORCE APPROVED VENDOR	ON	
EXPEDITE ITEM DETAILS	ON	
LEAD TIME	ON	BUSINESS
RESTRICT ITEMS BY PO TYPE	OFF	
STORES LOOKAHEAD REQUIRED DATE		PO
TEMPORARY STOCK STOREROOM	ON	TMP

Determine whether or not the system validates for account splits when the record is set to pending approval status.

For descriptions of the remaining rule keys please refer to the Purchase Order module configuration.

Option, Status, and Value

ACCOUNTS REQUIRED ON PENDING - This rule determines when the system checks for valid account splits on purchasing records. When it is set to ON, changing to Pending Approval status triggers the validation. When it is set to OFF the system validates accounts when the record is changed to Approved status. The default setting is "ON".

Custom LOV Notes for the Invoicing Module

When creating custom LOVs that function with the Pay to Vendor field on the Invoice header you need to ensure you are using the correct record group which were created to separate vendor Lists of Values:

1. PAY_TO_VENDOR_CODE_HDR should be used when function INVOICE PAY TO VENDORS is OFF in the Responsibility Module.
2. ALL_PAY_TO_VENDORS should be used when function INVOICE PAY TO VENDORS is ON in the Responsibility Module.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Display Accrual Tax Total

Grants the ability to see the accrued tax total on Invoice records.

Invoice Account Override

Grants the ability to change Invoice Line Item account numbers that were retrieved from

a Purchase Order.

Invoice - Override Discrepant

Grants the ability to change Invoice record status from Pending Resolution to Created status when a discrepancy still exists.

Invoice - Resolve Discrepant

Grants the ability to change Invoice record status from Pending Resolution to Created status after the discrepancy has been resolved (and before batch processing would make a similar status change).

Invoice Pay to Vendors

Grants the ability to select a different invoice pay to vendor than is indicated on the original Invoice.

Code Tables

Code Table 159: Federal Tax Codes (Length = 1)

Federal field - The code can only be one character long and the Description should contain the percentage rate in the first six characters of the field.

Code Table 160: State Tax Codes (Length = 1)

State field - The code can only be one character and the Description should contain the percentage rate in the first six characters of the field.

Code Table 161: Duty Codes (Length = 1)

Duty field - The code can only be one character long and the Description should contain the percentage rate in the first six characters of the field.

Code Table 157: Invoice Prorate Options

Prorate Options column - Define values for the Prorate Options field. Oracle Utilities Work and Asset Management pre-loads the standard selections: DISCOUNT, DUTY, EXTRA, FEDERAL TAX, FREIGHT, STATE TAX, but you can modify or add to this list.

Batch Processes

Invoice Resolution - sdbp_invoice-resolution;

Uses the INVOICE SETUP CRITERIA Business Rule for determining whether mismatched invoice processing is allowed, and tries to resolve mismatched invoices to PO receiving.

Cost Invoice - sdbp_cost_invoice.cost_invoice;

Processes costs for purchase Invoices, selecting approved Invoices and posting costs throughout the system as required. Once an Invoice is successfully processed, it is marked as posted.

Automatic Invoicing - sdbp_ers_invoicing;

Generates invoices based on records that are set for automatic invoicing.

Reports

S_RPT064 - Invoice Variance Report

Provides a summary of Invoices that vary from the Purchase Order.

S_RPT024 - Purchase Order Accruals (Unpaid Receipts) Report

Lists Purchase Orders with items that are not fully invoiced.

Invoice Batch Module

Fields

Sequence No.: Batch ID

The record number is comprised of a unique ID (Ex. "0000000000001"). Invoice Batch record numbers are typically set to be system generated.

TABLE NAME - SA_INVOICE_BATCH- The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 243: Process Level

Process Level Field - Establish codes that will define process groupings for your invoice batch procedures.

Warranty Claim Module

Fields

Sequence No.: Warranty No.

The record number is comprised of a unique ID (Ex. "0200070"). Warranty claim numbers are usually system generated.

TABLE NAME - SA_MFR_WARRANTY_CLAIM - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

CREATE WARRANTY CLAIM

Grants access to the action that creates a claim against a warranty in the Warranty module.

Batch Processes

Warranty Expiration Alerts - sdbp_process_warranty_alerts;

Sends an alert to the person indicated on the Warranty when the warranty expires.

Warranty Module

Fields

Sequence No.: Warranty No.

The record number is comprised of a unique ID (Ex. "0200070"). Warranty numbers must be system generated. Manual creation of these record numbers could result in critical system errors when WOs are created from other records or in batch procedures.

TABLE NAME - SA_MFR_WARRANTY - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Business Rules

Warranty Processing Rule

The screenshot shows a configuration window titled "Business Rule WARRANTY PROCESSING". It contains the following fields and controls:

- Rule ID: WARRANTY PROCESSING
- Business: Business
- List: List
- Limit?:
- Desc: This rule defines the special processing of the Warranty module.
- Comment: (Empty text area)
- Option table:

Option	Option Status	Value
SEND ALERT PRIOR TO EXPIRATION	ON	1

Description: This rule is used to control Warranty Expiration Alert processing for the Warranty module. A setting of On will enable the system to send an alert to the Warranty Administrator. You must specify the number of days, prior to

This rule controls warranty processing throughout the system.

Send Alert Prior to Expiration

Set this option to ON to have the system send an alert to the warranty administrator when the warranty is nearing expiration. You must specify the number of days prior to expiration that the alert is sent. Setting the option to OFF disables alerts.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

CREATE WARRANTY CLAIM

Grants access to the action that creates a claim against a warranty in the Warranty module.

Copy Record

WARRANTY - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Batch Processes

Warranty Expiration Alerts - sdbp_process_warranty_alerts;

Sends an alert to the person indicated on the Warranty when the warranty expires.

Cost Adjustment Module

Fields

Sequence No.: Adjustment ID

The record number is comprised of a unique ID (Ex. "00024"). Cost Adjustment record numbers are typically set to be system generated.

TABLE NAME - SA_ADJUSTMENT - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Next Approver Field

Designate approvers for Cost Adjustments in the Approval Limits module of the Administration subsystem under Approvals and Routes.

Business Rules

Cost Adjustments Rule

The screenshot shows a configuration window titled "Business Rule COST ADJUSTMENTS". It contains the following fields and controls:

- Rule ID:** COST_ADJUSTMENTS
- Business:** Business
- Parameter:** Parameter
- Limit?:**
- Desc:** This rule controls whether the adjustment quantity field is displayed on the adjustment screen.
- Comment:** (Empty text area)
- Field/Displayed Table:**

Field	Displayed
ADJUSTMENT QUANTITY	NO
- Description:** If this is YES then the quantity field will be displayed. This field is not used within Synergen but is used in interfaces. The quantity entered here is copied to the accounting log record.

The Cost Adjustments business rule controls whether the adjustment quantity field is displayed on the adjustment screen for use with interfaces.

Field and Displayed

If Displayed is set to YES then the Adjustment Quantity field will be displayed on the adjustment screen. This field is not used within Oracle Utilities Work and Asset Management but is used in interfaces. The quantity entered here is copied to the accounting log record.

Field and Displayed

If Displayed is set to YES, then the Adjustment Quantity field will appear on the cost adjustment screen. This field is not used within the system but can be used in the interfaces. The quantity amount will be populated on the accounting log.

Batch Processes

Asset Cost Allocation - sdbp_cost_asset;

Allocates costs to assets indicated on the Asset list in the Work Order Task module by creating cost adjustment records and posting accordingly.

Cost Adjustment for PM Route - sdbp_cost_route.cost_route;

Generates and posts cost adjustments to remove charges from the work order task account and distribute them among the PM Route's assets. Labor and material costs related to accomplishing the Scheduled PM Route are charged against the work order's task and then distributed amongst the assets that were finished on the PM Route.

Cost Adjustment - sdbp_cost_adjustment;

Processes adjustments costs that have not yet been posted.

Purchasing Log Module

The Purchasing Log module displays the log of Purchasing events.

Code Tables

Code Table 121: Purchasing Event Types

Event Type column - Define event types. System defined types are: EMAIL, PRINT, and STATUS.

Blanket Contract Log Module

The Blanket Contract Log module displays the log of Purchasing events.

Service Contract Module

Fields

Sequence No.: Contract

The record number is comprised of a unique ID (Ex. "0200002"). Service Contract record numbers are typically set to be system generated.

TABLE NAME - SA_SERVICE_CONTRACT- The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 35: Contract Category Codes

Category field - Define categories to classify Contract records. The two system values of DIRECT and INVENTORY cannot be removed or changed; but additional category codes can be defined. This is a system code table.

Copy Record

SERVCONTR - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Reports

S_RPT087 - Service Contract Accrued Cost Report

Provides a summary of accrued cost (invoiced) charges for Service Contracts.

S_RPT085 - Service Contract Details Report

Provides a detailed summary by rate type of estimated, committed, actual, and invoiced time charges (rates and hours) for Service Contracts.

S_RPT086 - Service Contract Summary Report

Provides a summary of estimated, committed, actual, and invoiced time charges for Contracts.

Service Contract Invoice Module

Code Tables

Code Table 700: Job Reference Codes

Job Ref. field - Define codes to provide unique identifiers for service timesheet records.

Business Rules

Serv Invoice Account Override Rule

The screenshot shows a configuration window titled "Business Rule SERV INVOICE ACCOUNT OVERRIDE". It contains the following fields and elements:

- Rule ID:** SERV INVOICE ACCOUNT OVERRIDE
- Business:** Business
- List:** List
- Limit?:**
- Desc:** This rule defines which users are authorized to change Service Invoice Line Item account numbers retrieved from a Service Contract Timesheet.
- Comment:** Username: Specify individuals by their USERNAME and use DEFAULT for all others. If DEFAULT is missing "DISALLOW" is assumed.
- Table:** A table with two columns: Username and Option Status.

Username	Option Status
BRANWEN	ALLOW
CKRAFT	ALLOW
DEFAULT	ALLOW
- Description:** A text area for additional details.

Define the users authorized to change Service Invoice Line Item account numbers retrieved from a Service Contract Timesheet.

Username and Option Status

For a user to override the account number on a Service Invoice, the user's username must be listed in the Username column with ALLOW in the Option Status column. If DEFAULT is entered in the Username column and the Option Status is ALLOW, then all users not listed will be allowed to change the Service Invoice Line Item account number. Alternately you can enter DISALLOW for Default and all users not listed will not be able to change the account number.

Serv Invoice Tolerances Rule

The screenshot shows a configuration window titled "Business Rule SERV INVOICE TOLERANCES". It contains the following fields and a table:

- Rule ID: SERV INVOICE TOLERANCES
- Business: Business
- Parameter: Parameter
- Limit?:
- Desc: This rule allows definition of both dollar and percent tolerance values for invoice matching processing.
- Comment: (Empty text area)
- Invoice Matching and Tolerance table:

Invoice Matching	Tolerance
DOLLAR	1
PERCENT	-10
RESULT	WARNING

- Description: The dollar variance allowed (Service Invoice Line Item vs. Line Item Rates) in whole dollars.

Define dollar and percent tolerance values for invoice matching processing.

Invoice Matching and Tolerance

DOLLAR - Enter the maximum (whole) dollar difference between the Service Invoice Line Item value and the Line Item Rate value that is allowed in the Tolerance column.

PERCENT - Enter the maximum (whole) percent difference between the Service Invoice Line Item value and the Line Item Rate value that is allowed in the Tolerance column.

RESULT - Enter either WARNING or STOP into the Tolerance column to either issue a warning message (and let the user continue) or to prevent the user from continuing when either tolerance is exceeded.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Serv Invoice Account Override

Grants the ability to change Service Invoice Line Item account numbers retrieved from a PO.

Service Invoice Export Wizard

Grants access to the action that allows users to export a file showing posted Service Invoice records and associated Timesheet details based on the selection criteria entered.

Batch Processes

Cost Service Invoice - sdbp_cost_service_invoice.cost_service_invoice;

Processes costs for service contract Invoices, selecting approved Invoices and posting costs throughout the system as required.

Accumulate Posted Service Timesheets - sdbp_process_service_timesheet.accumulate_posted;

Generates Service Contract Invoice records and associated Invoice Line Items for each Service Contract Timesheet in posted status with the Auto Pay indicator checked.

Service Contract Timesheets Module

Business Rules

Service Timesheet Charge Types Rule

Charge Type	Status	Lookup	Reference ID
A	ALLOW	REFERENCE ID	
E	ALLOW	ASSET	
F	ALLOW	ASSET/FUNCTION	
P	ALLOW	ASSET/PROCESS	
R	ALLOW	SERVICE REQUEST	
W	ALLOW	WORKORDER	

Determine the charge types for Service Contract Timesheets.

Charge Type

Create charge type codes in this column. These values should be a single, unique character (such as “A” for “Account” or “W” for “Work Order”).

Note: Charges based on an account number use the value in the Reference ID field as the Charge Number. Any account number you wish to directly charge time against must have a Reference ID. For more information regarding Reference ID's, please refer to the Account section of the Resource Users Guide.

Status

Enter ALLOW in this column to indicate that the CHARGE TYPE can be entered. Enter DISALLOW to indicate that the CHARGE TYPE cannot be entered.

Lookup

This column determines which database table is used to validate the associated Account Number (when labor charges are entered).

Reference ID

This column contains an optional default Account Number. If you enter a value into this column, then when a user charges time against this CHARGE TYPE, the Account Number entered here will default on the Service Contract Timesheet and may not be overridden. (This processing applies to charge types such as Sick Leave where you would not want users to enter any Account Number for sick time.)

Code Tables

Code Table 700: Job Reference Codes

Job Ref. field - Define codes to provide unique identifiers for service timesheet records.

Copy Record

CTIMESHT - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and

details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Copy Service Timesheet

Grants the ability to copy Service Timesheets using the Copy Service Timesheet action.

Copy to New Service Contract

Grants access to the action that makes a duplicate of an existing Service Contract record.

Service Contract to Active

Grants the authority to set a Service Contract record to Active status.

Batch Processes

Process Service Timesheet -

sdbp_process_service_timesheet.post_approved_time;

Processes approved labor costs (from service timesheets) that have not yet been posted. Costs are posted to the work order task as a Labor record. If a Labor Requirement record does not yet already exist for the task, the system inserts one, then posts the cost. Once a labor charge is successfully processed, it is marked as posted.

Checkout Request Module

Business Rules

Alerts Rule

Alert	Recipient
▲ BACKORDERED ITEMS HAVE ARRIVED	REQUESTOR
PARTS HAVE ARRIVED	REQUESTOR
PO ITEM RECEIVED	REQUESTOR
WORK ORDER HAS BEEN APPROVED	REQUESTOR

This business rule identifies system alerts that are available and who should receive the alert. New Alert types cannot be created.

Alert and Recipient

BACKORDERED ITEMS HAVE ARRIVED - Work Orders and Checkout Requests - Enter REQUESTOR in the Recipient column to have an alert sent to the requestor when backordered items come in. The requestor who's Issue Ticket Report has been printed will receive the alert.


PARTS HAVE ARRIVED - Work Order - Enter REQUESTOR or PLANNER in the RECIPIENT column to have an alert sent to the requestor or planner of a work order with a direct purchase is received in the Receiving module. The default is REQUESTOR. When this is set to PLANNER the alert is sent to the planner indicated on the work order task, not on the work order.

PO ITEM RECEIVED - Requisition - Enter REQUESTOR in the PO ITEM RECEIVED column to have an alert sent to the requestor identified on the Requisition when the requested PO item is received.

WORK ORDER HAS BEEN APPROVED - Work Order - Enter REQUESTOR in the RECIPIENT column to have an alert sent to the work order requestor when approval has been processed for the work order.

WO FINISH WITH OPEN PO OR REQ - Purchase Order, Requisition - Enter the person who should receive an alert when a Work Order that references an open purchase order or requisition is set to Finished status. The Default setting is to BOTH.

Bar Code Configuration Rule



Business Rule BAR CODE CONFIGURATION

Rule ID: Configuration: List: Limit?

Desc: This business rule will determine which menu items will be available in RFGen.

Comment:

Menu Item	Display
CHECKOUTS:RETURNS	ON
LABEL PRINTING	ON
MULTI-STEP RECEIVING	ON
PHYSICAL INVENTORY	ON
RECEIVING	ON
REORDER HANDLING	ON
STOCK TRANSFERS	ON
STOCKING	ON

Description: Checkouts>Returns menu item in RFGen.

This rule determines the main menu options available in the RFGen Bar Coding application.

Menu Item and Display

Options set to ON appear on the bar coding main menu.

Checkout Request Rule

Define processing in the Checkout Requests module.

Processing	Option Status	Value
ALLOW PARTIAL ISSUE	YES	
AUTO PICK QUEUE	NO	14
CHANGE STOREROOM AT CHECKOUT	NO	
NEGATIVE QUANTITY	YES	
PRINT RESTRICTIONS	NO	
REPRINT	YES	

Description
Enter YES into the "OPTION STATUS" column to allow partial issue of a checkout request. When this option is set to YES, the system will not set the checkout request item status to ISSUED, it will remain in REQUESTED status. Also

Processing, Option Status, and Value

ALLOW PARTIAL ISSUE - This rule key determines how the system handles partial issue of items on a checkout request. If this option is set to NO and items are partially issued against a checkout request the system sets the status of the checkout request to Closed and the item status to Issued. With this setting, the system also removes the remaining demand from the storeroom. If this option is set to YES and items are partially issued against a checkout request, the checkout request remains in Active status and the Item status remains in Requested status. With this setting, the system only removes demand from the storeroom for the items that have been issued.

AUTO PICK QUEUE - (AMMO only) This rule key is used by batch and online processing to determine if the checkout requests should automatically be put on the pick queue when Advanced Materials Option is utilized.

CHANGE STOREROOM AT CHECKOUT - Enter YES or NO into the Option Status column to allow or disallow changing the Storeroom for line items during the checkout process. If this option is set to YES, the system allows users to modify the storeroom during checkout, provided the item has not been partially issued. The default setting is NO.

If the storeroom is changed:

- The system automatically updates the displayed quantity and pricing information in accordance with the new storeroom.
- The system records this change in the Storeroom log (sa_storeroom_log).
- The batch procedure, sdbp_storeroom_demand(###,###), must be run to clear the demand from the original storeroom and ensure that the true demand against the on-hand quantity is not distorted. The batch procedure can run as part of Run All Batch or as a standalone process.

NEGATIVE QUANTITY - Enter YES or NO into the Option Status column to allow or disallow a negative quantity to be entered on a checkout request. This processing does not affect the storeroom quantity levels. This is a flag to alert the storeroom that an item needs to be returned to stock.

Items must be returned to stock in the Stock Checkout module.

PRINT RESTRICTIONS - Enter YES into the Option Status column to allow a checkout request to be changed once it has been printed. Enter NO into the Option Status column

to disallow a checkout request to be changed once it has been printed.

REPRINT - Enter YES into the Option Status column to allow a checkout request to be printed more than once. Enter NO into the Option Status column to disallow a checkout request to be printed more than once.

Storeroom Demand Allocation Rule

The screenshot shows a configuration window titled "Business Rule STOREROOM DEMAND ALLOCATION". It includes fields for Rule ID, Desc, and Comment. Below these is a table with columns for Option, Status, and Value. The table contains the following data:

Option	Status	Value
CHECKOUT REQUEST DEMAND	YES	
EXPIRATION OF REQUEST DEMAND	NO	14
INCLUDE RFQ	YES	
RESOLVE UNSUPPORTED ALLOCATION	NO	

Below the table is a Description field with the text: "This will enable the demand quantity for checkout requests that are not already set from a work order. The requested quantities for OPEN requests will be included in the on demand quantity."

Set up processing for storeroom demand and allocation.

Option, Status and Value

CHECKOUT REQUEST DEMAND - (YES/NO) If this rule key is set to YES, checkout requests in ACTIVE status will be counted in the demand quantity shown in the Storeroom Pricing view of the Storeroom module, and will be factored in whenever storeroom demand is calculated. If the rule key is set to NO checkout requests will not be included in any demand quantity calculations. If the rule key is changed from NO to YES the system does not recalculate existing quantities, but will begin to include ACTIVE checkout requests in calculations made after the change.

INCLUDE RFQ - This rule key determines whether the quantity on Request for Quotes line items in CREATED, APPROVED or ISSUED status which originated from an Approved Requisition are to be included in the Pending Order quantity field on the Storeroom Pricing screen.

EXPIRATION OF REQUEST DEMAND - (Advanced Materials Management Option ONLY).

RESOLVE UNSUPPORTED ALLOCATION - (Advanced Materials Management Option ONLY).

Variable Expense Codes Rule

Rule	Option
DISPLAY EXPENSE CODES	YES
FORCE UNIQUE EXPENSE CODES	NO
OVERRIDE EXPENSE CODES	NO

This rule determines how expense codes are handled during stock checkout, checkout request, planning work order task materials and labor, and in the Timekeeping module. Regardless of the settings in this rule, any desired changes to expense codes can only be made before costs are actualized. Once actual costs are applied, the expense code on the record cannot be changed.

Rule and Option

DISPLAY EXPENSE CODES - If you enter YES as the option, the system will display the Regular and Premium Expense Code fields on the employee Timesheet, and the Expense Code field on the Issue Ticket for stock checkouts based on Work Orders. Enter NO and the field is not displayed.

FORCE UNIQUE EXPENSE CODES - If you enter YES for this option, work order time charges for the same craft must have the same expense codes. The default setting is YES.

OVERRIDE EXPENSE CODES - Enter YES or NO in the OPTION column to allow or disallow users to change expense codes on timesheets, issue tickets for stock checkout, stock checkout requests, and material and labor detail records on work order tasks.

Entering YES in the OPTION column has the following implications:

- Materials planners will be able to overwrite the default expense codes for the Materials view of the Work Order module in the Maintenance subsystem. The system defaults this information from expense code associated with the Stock Code and Storeroom.
- Employees responsible for creating Issue tickets for stock item checkouts will be able to change the associated Expense code.
- The system will display the Regular and Premium Expense Code fields on the employee Timesheet, and the Expense Code field on the Issue Ticket for sock checkouts based on Work Orders. This includes expense codes that have been provided by planners.
- Labor planners will be able to overwrite the default expense codes for Regular and Premium labor on Work Order Tasks. The system defaults this information from the Craft associated with the Work Order Task.

-
- Workers who enter their own time into the Timekeeping module of the Maintenance subsystem, will be able to change the Regular and Premium labor information brought over from the Work Order Task on timesheet entries based on Work Orders. This includes expense codes that have been provided by planners.
 - Supervisors who review timesheets will be able to change the Regular and Premium labor information brought over from the Work Order Task on timesheet entries based on Work Orders. This includes expense codes that have been provided by planners and/or changed by employees on their timesheets.

Combining the Rules:

To keep anyone from changing expense codes:

Display Expense Codes = NO

Force Unique Expense Codes = YES

Override Expense Codes = NO

To allow only Planners to use variable expense codes:

Display Expense Codes = NO

Force Unique Expense Codes = YES

Override Expense Codes = YES

To allow charges for the same craft to use different expense codes:

Display Expense Codes = YES

Force Unique Expense Codes = NO

Override Expense Codes = YES

Code Tables

Code Table 7: Deliver To Location (Length = 10)

Deliver to Location field - Define codes to designate possible delivery locations within your organization. Typical entries include: "North side loading dock" or "Main Warehouse".

Code Table 100: Checkout Request Priority (Length = 2)

Priority field - Define codes to prioritize checkout requests. Examples include: (1-Regular, 2-Urgent, 3-Emergency).

Copy Record

CHKREQST - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Add Items From Work Order

Grants access to the Add Items from Work Order and Select Items from Work Order actions when a checkout request is in Created status. The list of items comes from the material requirements on the Work Order.

Activate Checkout Request from Schedule

Users with this responsibility will have available a column of check boxes in the Checkout Request view of the Daily Schedule module as well as an action which allows users to activate the checkout requests from the scheduling record.

Reports

S_RPT026 - Inventory Picklist Report

Lists Stock items to be issued from the storeroom and can be used to provide storeroom personnel a means to prepare Stock for pickup or delivery. This list can be built by either planning Stock items on a work order before the work order is activated or by creating a Checkout Request record.

Note: S_RPT026B is the bar code font version of this report.

Stock Checkout Module

Business Rules

Checkout Allowable Charge Type Rule

This rule is used to control the charge types that are allowable for Stock Checkouts. A setting of ALLOW for a Charge Type makes it available on the checkout screen. A setting of DISALLOW will exclude the Charge Type from the checkout screen

The screenshot shows the configuration window for the Business Rule 'CHECKOUT ALLOWABLE CHARGE TYPE'. The Rule ID is 'CHECKOUT_ALLOWABLE_CHARGE_TYPE', the Business is 'Business', and the Limit? checkbox is unchecked. The Description is 'This rule is used to control the charge types that are allowable for Stock Checkouts.' and the Comment is 'A setting of ALLOW for a Charge Type makes it available on the checkout screen. A setting of DISALLOW will exclude the Charge Type from the checkout screen.' The main table lists Charge Types and their Status:

Charge Type	Status
A	ALLOW
C	ALLOW
E	ALLOW
P	ALLOW
S	ALLOW
W	ALLOW

At the bottom, there are fields for Description and Account Number.

Checkout Processing Rule

The screenshot shows the configuration window for the Business Rule 'CHECKOUT PROCESSING'. The Rule ID is 'CHECKOUT_PROCESSING', the Business is 'Business', the Parameter checkbox is checked, and the Limit? checkbox is unchecked. The Description is 'This rule controls various options for checkout.' and the Comment field is empty. The main table lists Checkout Options and their Option Status:

Checkout Option	Option Status
CHECKOUT_TO_FINISHED_WO	YES
RETURN MORE THAN ISSUED	NO
	YES

At the bottom, there is a Description field with the text: 'This controls users' ability to issue stock and tools against a finished Work Order.'

Control whether checkouts against work orders in Finished status are allowed. Note that you can always return items against a Finished work order.

Values that are not described below but that are shown on the Batch Stock Reorder Business Rule list are only used with the Advanced Material Management option.


Checkout Option and Option Status

CHECKOUT_TO_FINISHED_WO - This option controls users' ability to issue stock and tools against a finished Work Order. When this option is set to YES, the list of values for Work Order tasks will only show tasks in Active status. If it is set to NO the list will show

tasks in both Active and Finished status.

RETURN MORE THAN ISSUED - If this rule key value is set to YES, users are able to use the Stock Checkout module to return more than what was issued against a work order.

Barcoding Checkout Rule



Barcoding Upload	Option Status
UPLOAD ERRORS	ON

Allow deletion of entries from the temporary upload table before the database is updated.

This allows you to decide whether the temporary upload table should be empty prior to next upload of the checkout/return data via a handheld or if new entries should be appended to the prior error entries.

This rule supports a specific interface to the Intermec Janus 2020 (c) hand-held bar code scanner.

Barcoding Upload and Option Status

UPLOAD ERRORS - Enter ON in the OPTION STATUS column to allow records with errors to be kept in a temporary table. Enter OFF in the OPTION STATUS column to remove the remaining records from the temporary table prior to the next upload.

Optional Message Presentation Rule

Business Rule OPTIONAL MESSAGE PRESENTATION

Rule ID: Configuration: Parameter: Limit?

Desc: This rule dictates where specific messages should be sent: to the bottom of the current window or to an Alert.

Comment: This processing applies to only certain types of messages; all other messages are directed by pre-determined processing.

Message	Type
CHECK PRIVS	ON
ERROR MESSAGES	ALERT
EXIT MODIFIED RECORD	ALERT
REQUIRED FIELD COLOR	DEFAULT
STOCK CHECKOUT WARNING	ON

Description

ON: Table-level privilege check is made by Synergen Series as soon as the user begins to insert a record.
 OFF: Table-level privilege checks are made by Oracle at the time the record is saved.

Indicate when and how certain system messages are displayed.

This processing applies to only certain types of messages; all other messages are directed by pre-determined processing.

Message and Type

STOCK CHECKOUT WARNING - Enter ON in the Type column for the system to display a message that the issue quantity on the Work Order Checkout Request record is greater than the estimated quantity on the Work Order Task Material Requirements. This message does not prevent the checkout; it is merely a warning. Enter OFF to prevent the message.

This is the only rule key that applies to the Stock Checkout module. For a description of other keys, please refer to the Administration section.

Variable Expense Codes Rule

Business Rule VARIABLE EXPENSE CODES

Rule ID: Configuration: Parameter: Limit?

Desc: This rule is used to allow the ability to change expense codes during stock checkout and planning of Work Order Materials until the expense codes are actual.

Comment:

Rule	Option
DISPLAY EXPENSE CODES	YES
FORCE UNIQUE EXPENSE CODES	NO
OVERRIDE EXPENSE CODES	NO

Description

This rule determines how expense codes are handled during stock checkout, checkout request, planning work order task materials and labor, and in the Timekeeping module. Regardless of the settings in this rule, any desired changes to expense codes can only be made before costs are actualized. Once actual costs are applied, the expense code on the record cannot be changed.

Rule and Option

DISPLAY EXPENSE CODES - If you enter YES as the option, the system will display the Regular and Premium Expense Code fields on the employee Timesheet, and the Expense Code field on the Issue Ticket for stock checkouts based on Work Orders. Enter NO and the field is not displayed.

FORCE UNIQUE EXPENSE CODES - If you enter YES for this option, work order time charges for the same craft must have the same expense codes. The default setting is YES.

OVERRIDE EXPENSE CODES - Enter YES or NO in the OPTION column to allow or disallow users to change expense codes on timesheets, issue tickets for stock checkout, stock checkout requests, and material and labor detail records on work order tasks.

Entering YES in the OPTION column has the following implications:

- Materials planners will be able to overwrite the default expense codes for the Materials view of the Work Order module in the Maintenance subsystem. The system defaults this information from expense code associated with the Stock Code and Storeroom.
- Employees responsible for creating Issue tickets for stock item checkouts will be able to change the associated Expense code.
- The system will display the Regular and Premium Expense Code fields on the employee Timesheet, and the Expense Code field on the Issue Ticket for sock checkouts based on Work Orders. This includes expense codes that have been provided by planners.
- Labor planners will be able to overwrite the default expense codes for Regular and Premium labor on Work Order Tasks. The system defaults this information from the Craft associated with the Work Order Task.
- Workers who enter their own time into the Timekeeping module of the Maintenance subsystem, will be able to change the Regular and Premium labor information brought over from the Work Order Task on timesheet entries based on Work Orders. This includes expense codes that have been provided by planners.
- Supervisors who review timesheets will be able to change the Regular and Premium labor information brought over from the Work Order Task on timesheet entries based on Work Orders. This includes expense codes that have been provided by planners and/or changed by employees on their timesheets.

Combining the Rules:

To keep anyone from changing expense codes:

Display Expense Codes = NO

Force Unique Expense Codes = YES

Override Expense Codes = NO

To allow only Planners to use variable expense codes:

Display Expense Codes = NO

Force Unique Expense Codes = YES

Override Expense Codes = YES

To allow charges for the same craft to use different expense codes:

Display Expense Codes = YES

Force Unique Expense Codes = NO

Override Expense Codes = YES

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Checkout All Planned Items

Grants access to the Checkout All action in the Stock Checkout module.

Reports

S_RPT020 - Issue Ticket Report

Lists Stock items issued during a single session in the Stock Checkout module, Inventory subsystem. The Stock Checkout module is used to process issues and returns of stock items from and to a storeroom.

Stock Transfer Module

Business Rules

Alerts Rule

Alert	Recipient
▲ BACKORDERED ITEMS HAVE ARRIVED	REQUESTOR
PARTS HAVE ARRIVED	REQUESTOR
PO ITEM RECEIVED	REQUESTOR
WORK ORDER HAS BEEN APPROVED	REQUESTOR
▼	

Description
Enter REQUESTOR into the "RECIPIENT" column to have an alert sent to the requestor of the work order or the checkout request when stock items have arrived that were on backorder.

This business rule identifies system alerts that are available and who should receive the alert. New Alert types cannot be created.

Alert and Recipient

BACKORDERED ITEMS HAVE ARRIVED - Work Orders and Checkout Requests - Enter REQUESTOR in the Recipient column to have an alert sent to the requestor when backordered items come in. The requestor who's Issue Ticket Report has been printed will receive the alert.


PARTS HAVE ARRIVED - Work Order - Enter REQUESTOR or PLANNER in the RECIPIENT column to have an alert sent to the requestor or planner of a work order with a direct purchase is received in the Receiving module. The default is REQUESTOR. When this is set to PLANNER the alert is sent to the planner indicated on the work order task, not on the work order.

PO ITEM RECEIVED - Requisition - Enter REQUESTOR in the PO ITEM RECEIVED column to have an alert sent to the requestor identified on the Requisition when the requested PO item is received.

WORK ORDER HAS BEEN APPROVED - Work Order - Enter REQUESTOR in the RECIPIENT column to have an alert sent to the work order requestor when approval has been processed for the work order.

WO FINISH WITH OPEN PO OR REQ - Purchase Order, Requisition - Enter the person who should receive an alert when a Work Order that references an open purchase order or requisition is set to Finished status. The Default setting is to BOTH.

Bar Code Configuration Rule




Menu Item	Display
CHECKOUTS:RETURNS	ON
LABEL PRINTING	ON
MULTI-STEP RECEIVING	ON
PHYSICAL INVENTORY	ON
RECEIVING	ON
REORDER HANDLING	ON
STOCK TRANSFERS	ON
STOCKING	ON

This rule determines the main menu options available in the RFGen Bar Coding application.

Menu Item and Display

Options set to ON appear on the bar coding main menu.

Receiving Configuration Rule



Receiving Parameters	Options	Contact Emp.
ADD TAX AT RECEIPT	NO	
BACKORDER PROCESSING CHECK	ON	
RECEIVE MORE THAN ORDERED	YES	

This rule allows users to set parameters related to the Receiving, Multi-Step Receiving, and Stock Transfer modules.

Receiving Parameters and Options

ADD TAX AT RECEIPT - Set this key to YES to have the system calculate the average unit price for items by including taxes and exchange rates included in the final invoiced price. This allows the system to reflect the true cost of procurement of the item. When the key is set to NO taxes are not factored into the cost.

BACKORDER PROCESSING CHECK - This rule key allows you to enable or disable checking of backordered items in the Receiving, Multi-Step Receiving, and Stock Transfer

modules. Set this option to ON if you want the system to prompt the user with a listing of Checkout Requests and Work Orders that require the backordered item when other items on the Purchase Order are received.

Reports

S_RPT115 - Stock Transfer Report


Lists Stock items to be issued from one storeroom and received in another.

Note: S_RPT115B is the bar code font version of this report.

Storeroom Stocking Module

Business Rules

Bar Code Configuration Rule



Menu Item	Display
CHECKOUTS:RETURNS	ON
LABEL PRINTING	ON
MULTI-STEP RECEIVING	ON
PHYSICAL INVENTORY	ON
RECEIVING	ON
REORDER HANDLING	ON
STOCK TRANSFERS	ON
STOCKING	ON

This rule determines the main menu options available in the RFGen Bar Coding application.

Menu Item and Display

Options set to ON appear on the bar coding main menu.

Reorder Review Module

When inventory levels for a stock item fall below reorder points you have set, the system automatically creates Reorder Review records for the stock item, provided that you have marked the item for reorder review in the storeroom. Reorder Review records include the quantity that batch processing has determined must be ordered to increase the current inventory to the maximum level, along with other information from the Storeroom record. Once reorder records are approved by a reviewer, batch processing completes the processing by generating the appropriate purchasing document.

Business Rules

Batch Stock Reorder Rule

Business Rule BATCH STOCK REORDER

Rule ID: BATCH STOCK REORDER Business Parameter Limit?

Desc: This rule lets you turn stock reorder ON and OFF, choose the document type, the status the document is created in and quantity rounding.

Comment: Batch processing.

Batch Processing	Values
ALERT_ADDRESSEE_NAME	RAY
ALLOCATED_DEMAND	
DEFAULT_DOCUMENT	PO
DEF_BUYER_CODE	DOG
DEF_DUTY_CODE	0
DEF_FEDERAL_TAX_CODE	0
DEF_STATE_PROVINCE_TAX_CODE	0
EXCEED_MAX_BY_DEMAND	ON
GROUP_BY_BUYER	OFF
HISTORICAL_USAGE_ANALYSIS	
INSPECTION_HOLDS	
INVENTORY_CARRYING_COST	
NUMBER_OF_VENDORS	3

Description: User Name to whom an Alert will be sent for Stock Items with Auto Reorder Indicator = C (contact).

Control several of the re-order processing elements using this rule. These include turning automatic stock reorder processing on or off, the type of document to be produced by stock reorder (Purchase Order or Requisition, including setting the default buyer, federal tax and state tax codes), the status that document is to be created in, and whether to round the order quantity up or down.

Batch Processing and Values

ALERT_ADDRESSEE_NAME - The username for the person who will receive an Alert when batch selects stock items with an Auto Reorder Indicator of "C" (Contact).

ALLOCATED_DEMAND (Advanced Materials Management Option) - Determines whether the system will include allocated demand quantities in the calculation for Available Quantity. This option is only used when reorder method is set to option 2.

DEFAULT_DOCUMENT - Determines the type of document to be created. Enter PO in the VALUES column to generate Purchase Orders. Enter REQ in the VALUES column to generate Requisitions or RFQ in the VALUES column to generate a Request for Quote.

DEF_BUYER_CODE - Default Buyer Code that will appear on the created document. In some instances this value MUST be set so that automatic reorder will function properly. If the Reorder Type field on the Reorder Review record is set to Reorder Review or Auto-Reorder and this value is left blank, the intended purchasing document is not created, even if the Buyer field is populated on the Master Catalog and/or Storeroom.

DEF_DUTY_CODE - Default Duty Code that will appear on the created document.

DEF_FEDERAL_TAX_CODE - Default Federal Tax Code that will appear on the created document.

DEF_STATE_PROVINCE_TAX_CODE - Default State/Provincial Tax code that will appear on the created document.

EXCEED MAX BY DEMAND - determines how much the system orders on automatic reorder. If this rule key is set to ON, the system orders enough to reach the maximum allowed quantity plus the amount that is on demand. On demand quantity is defined as the demand placed on the storeroom from active work orders and checkout requests. Setting the rule key to ON insures that stores will remain at the maximum level after the demand has been fulfilled.

If the rule key is set to OFF the system only orders enough to reach the maximum, regardless of how demand may later affect stores quantities. Setting the rule key to OFF could mean that stores will need to be ordered more frequently and you can therefore expect to issue more purchasing documents. However, this setting could also prevent the system from ordering against demand that may never actually result in items being removed from the storeroom.

GROUP BY BUYER - Turns ON or OFF the use of buyer code from the catalog to group items on PO's or Requisitions. The default is OFF.

HISTORICAL_USAGE_ANALYSIS (Advanced Materials Management Option)- The number of months to use for average daily usage analysis. This number is used for reorder recommendations. Only used when reorder method is set to Option 2.

INSPECTION_HOLDS (Advanced Materials Management Option) - Used in the calculation for available quantity during batch stock reorder. Only used when reorder method is set to option 2.

INVENTORY_CARRYING_COST (Advanced Materials Management Option) - Calculate the Economic Order Quantity of a storeroom. Only used when reorder method is set to option 2.

NUMBER OF VENDORS - Represents the number of vendors the system will create for the RFQ Bidders List. Only used when the Value in DEFAULT_DOCUMENT is RFQ.

ON DEMAND QUANTITY INCLUDED - determines when the system triggers automatic reorder. If the rule key is set to ON the system subtracts the on demand quantity from the available quantity to determine whether or not stores have fallen below the reorder point. On demand quantity is defined as the demand placed on the storeroom from active work orders and checkout requests. This setting can reduce the number of purchasing documents that are generated because it anticipates future stores depletion as well as taking into account actual stores depletion.

If the rule key is set to OFF, only the available quantity in the storeroom is considered in determining whether or not stores should be reordered. This setting may prevent the system from ordering against demand that never results in items being removed from the storeroom.

PENDING DISPOSITION INCLUDED - Determines if the pending disposition quantity should be included in the on hand quantity for reorder calculations. The default is ON.

PLANNED_ORDERS - Used in the calculation for Available Quantity during batch stock reorder. Only used when reorder method is set to option 2.

PO_PROCESSING_COST_AUTO (obsolete - Advanced Materials Management Option)

only) - The cost for automatically processing a stores reorder PO. This number is used to calculate the Economic Order Quantity of a storeroom. Only used when reorder method is set to option 2.

PO_PROCESSING_COST_CONTACT (obsolete - Advanced Materials Management Option only) - The cost for processing a stores reorder PO with contact. This number is used to calculate the Economic Order Quantity of a storeroom. Only used when reorder method is set to option 2.

PO_PROCESSING_COST_REVIEW (obsolete - Advanced Materials Management Option only) - The cost for processing a stores reorder PO with reorder review. This number is used to calculate the Economic Order Quantity of a storeroom. Only used when reorder method is set to option 2.

PO STATUS - Purchase Orders may be automatically created in one of three statuses: CREATED, APPROVED and ISSUED. Enter the desired status in the VALUES column.

REORDER_METHOD - Set to Option 1. Before the AMMO rule keys became obsolete, this rule key determined whether AMMO was turned on (Option 2) or off (Option1).

REPAIR QUANTITY INCLUDED - Determines if the repair quantity should be included in the on-hand quantity.

REQUISITION CHECK - If set to ON, items on a valid requisition will not be included in Batch Stock Reorder. Related to Rule - REQUISITION STATUS.

REQUISITION STATUS - The status to be used when batch generates a Requisition. Only used when the Value in DEFAULT_DOCUMENT is REQ.

RFQ REQUIRED DATE LEADTIME - The system will use the value entered here to calculate the Required Date on RFQ records that are generated by batch. The Required Date will be calculated as (Sysdate + value). This is only used when the reorder method is set to option 2.

REQUIRED_DATE_BY_LEAD_TIME - (obsolete - Advanced Materials Management Option only)

RFQ STATUS - The status to be used when batch generates a Request for Quote. Only used when the Value in DEFAULT_DOCUMENT is RFQ.

ROUNDING - Dictates whether to round the order quantity up or down with respect to the Maximum (Storeroom) Quantity and the Purchase Quantity. Setting the VALUES column to UP indicates that the reorder quantity may exceed Maximum Quantity by Purchase Quantity minus 1 (rounding up). Setting the VALUES column to DOWN indicates that the reorder quantity will reach but never exceed Maximum Quantity (rounding down).

STOREROOM REORDER PROCESSING - Allows the user to choose which default tax and buyer information will be used for re-order processing. Select either Master Catalog (CATALOG) or Storeroom (STOREROOM).

If a Buyer and Taxes are entered in the Storeroom Override view in the Storeroom module, these values are used when the system creates POs or Requisitions even if a Blanket Contract is referenced.

The Ship to Code on Purchase Orders and Requisitions is set to the storeroom item being ordered. Note that there will only be one storeroom (multiple items) per Purchase Order or Requisition.

UNALLOCATED_DEMAND - Used in the calculation for Available Quantity during batch stock reorder. Only used when reorder method is set to option 2.

Batch Processes

Stock Reorder - sdbp_stock_reorder.stock_reorder;

Reviews all storeroom items, selecting those that are set up for automatic reorder and processes those items that have reached their reorder point. This process uses settings in the Batch Stock Reorder Business Rule to calculate the quantity to reorder. The basic calculation is:

$$\text{reorder_quantity} = \text{maximum_quantity} - (\text{inventory_quantity} + \text{in receipt quantity} + \text{on_order_quantity} + \text{reorder_quantity} + \text{repair_quantity})$$

You can set a custom batch process to run SDBP_STOCK_REORDER on a specific storeroom by entering that storeroom in the job parameters.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Reorder Wizard

Grants the ability to create and approve reorder records.

Reports


S_RPT028 - About to Reorder Report

Lists storeroom items due for reorder.

Receiving Module

Business Rules

Alerts Rule



Alert	Recipient
▲ BACKORDERED ITEMS HAVE ARRIVED	REQUESTOR
PARTS HAVE ARRIVED	REQUESTOR
PO ITEM RECEIVED	REQUESTOR
WORK ORDER HAS BEEN APPROVED	REQUESTOR
▼	

This business rule identifies system alerts that are available and who should receive the alert. New Alert types cannot be created.

Alert and Recipient

BACKORDERED ITEMS HAVE ARRIVED - Work Orders and Checkout Requests - Enter REQUESTOR in the Recipient column to have an alert sent to the requestor when backordered items come in. The requestor who's Issue Ticket Report has been printed will receive the alert.

PARTS HAVE ARRIVED - Work Order - Enter REQUESTOR or PLANNER in the RECIPIENT column to have an alert sent to the requestor or planner of a work order with a direct purchase is received in the Receiving module. The default is REQUESTOR. When this is set to PLANNER the alert is sent to the planner indicated on the work order task, not on the work order.

PO ITEM RECEIVED - Requisition - Enter REQUESTOR in the PO ITEM RECEIVED column to have an alert sent to the requestor identified on the Requisition when the requested PO item is received.

WORK ORDER HAS BEEN APPROVED - Work Order - Enter REQUESTOR in the RECIPIENT column to have an alert sent to the work order requestor when approval has been processed for the work order.

WO FINISH WITH OPEN PO OR REQ - Purchase Order, Requisition - Enter the person who should receive an alert when a Work Order that references an open purchase order or requisition is set to Finished status. The Default setting is to BOTH.

Bar Code Configuration Rule

Business Rule BAR CODE CONFIGURATION

Rule ID: BAR CODE CONFIGURATION Configuration List Limit?

Desc: This business rule will determine which menu items will be available in RFGen.

Comment:

Menu Item	Display
CHECKOUTS/RETURNS	ON
LABEL PRINTING	ON
MULTI-STEP RECEIVING	ON
PHYSICAL INVENTORY	ON
RECEIVING	ON
REORDER HANDLING	ON
STOCK TRANSFERS	ON
STOCKING	ON

Description: Checkouts>Returns menu item in RFGen.

This rule determines the main menu options available in the RFGen Bar Coding application.

Menu Item and Display

Options set to ON appear on the bar coding main menu.

Default Directories Rule

Business Rule DEFAULT DIRECTORIES

Rule ID: DEFAULT DIRECTORIES Business Parameter Limit?

Desc: This rule defines default directories

Comment: This rule is used when performing client-side operations

Directory	Path
BAR CODE LABEL DROP DIRECTORY	c:\of
INSTALLED DIRECTORY	c:\sy
OPER DATA EXPORT DIRECTORY	c:\er
OPER DATA IMPORT DIRECTORY	c:\er
RFQ EXPORT DIRECTORY	c:\er
RFQ IMPORT DIRECTORY	c:\er

Description: This is the default directory to put barcode label files into

Define default directories for use when performing client-side operations.


Directory

COMPONENT UPLOAD DIRECTORY - This is the directory where files are stored when they are uploaded to support receiving multiple trackable components.

Path

This is the hard drive storage location for the corresponding file.

Enforce Receiver Rule



Functional Authority	Option Status
APPROVER	ALLOW
ISSUER	ALLOW

Description
Allows the approver of Purchase Orders to perform the receiving session for those Purchase Orders.


Determine whether or not the issuer and/or approver of a Purchase Order are allowed to perform the receiving session for the PO that the issued or approved.

Functional Authority and Option Status

APPROVER - By setting the OPTION STATUS column to ALLOW, you give the approver of Purchase Orders the ability to also receive the items. To prevent receiving, set the OPTION STATUS column to DISALLOW.

ISSUER - By setting the OPTION STATUS column to ALLOW, you give the issuer of Purchase Orders the ability to also receive the items. To prevent receiving, set the OPTION STATUS column to DISALLOW.

Receiving Configuration Rule



Receiving Parameters	Options	Contact Emp.
ADD TAX AT RECEIPT	NO	
BACKORDER PROCESSING CHECK	ON	
RECEIVE MORE THAN ORDERED	YES	

Description
Add Tax at Receipt, will determine whether the Purchase Order Line Item taxes will be included into the receiving Storeroom's total value for the Stock Code being received to calculate the Average Unit Price. If the key value is set

This rule allows users to set parameters related to the Receiving, Multi-Step Receiving, and Stock Transfer modules.

Receiving Parameters and Options

ADD TAX AT RECEIPT - When this rule key is set to YES the system calculates the average unit price for stock items by including any taxes and exchange rates included in the final invoiced price. This allows the system to reflect the true cost of procurement of the item. When the key is set to NO taxes are not factored into the cost.

BACKORDER PROCESSING CHECK - This rule key allows you to enable or disable checking of backordered items in the Receiving, Multi-Step Receiving, and Stock Transfer

modules. Set this option to ON if you want the system to prompt the user with a listing of Checkout Requests and Work Orders that require the backordered item when other items on the Purchase Order are received.

RECEIVE ALL INCLUDES S - Set to YES or NO to indicate whether or not 'S' (Services) type Purchase Order line items are included in the list of items to be processed when the 'Receive All Items as Ordered' action is invoked.

RECEIVE ALL INCLUDES X - Set to YES or NO to indicate whether or not 'X' (Misc. Costs) type Purchase Order line items are included in the list of items to be processed when the 'Receive All Items as Ordered' action is invoked.

RECEIVE MORE THAN ORDERED - This rule key controls whether or not users can receive quantities that exceed the quantity ordered on a purchase order. The setting applies to items received in the Receiving module or the Multi-Step Receiving module. If the key is set to YES (default), quantities greater than the PO item quantity can be received without any warnings or errors being displayed. If the key is set to NO, any attempt to receive quantities greater than the PO item quantity results in an error. If the key is set to RESTRICT, only authorized users can receive quantities that exceed the PO item quantity. Authorization is granted by adding the Receive More Than Ordered function to a user's responsibilities. The Contact Emp. field indicates the person who is primarily responsible for providing authorization to restricted users when needed. The list of values for this list is populated with the name of any user that has the Receive More Than Ordered function in their responsibility profile. When the item is received, the system prompts the authorized user for their username and PIN to authorize the receipt.

Specification Upload Defaults

This rule defines default values to be used by the Component Specification Upload Wizard in the Component ID module. The wizard creates Specification records from a data upload and attaches the specifications to existing Component records. Setting the default specification type, category and description in this rule ensures that new Specification records can be created by the upload process without errors.

The screenshot shows a configuration window titled "Business Rule SPECIFICATION UPLOAD DEFAULTS". It includes a table with the following data:

Column Name	Parameter
SPECIFICATION_CATEGORY	ENV
SPECIFICATION_DESC	not used
SPECIFICATION_TTYPE	ENG

The combination of specification type and category must match a type and category combination defined in the Specification Template module.

To use this functionality, sequence numbering for SA_SPECIFICATION_DATA and SA_COMPONENT_ID must be system generated. Open the Sequence Numbers module and make sure that there is a check in the Sys column for these tables.

Note that the SPECIFICATION_DESC parameter uses the Description as the user entered value rather than the Key Value. This is different than the other two parameters

which use Key Value as the user defined string.

Web Configuration Rule

Rule	Option	Setting
REPORTS ALWAYS PREVIEW	YES	
REPORTS CUSTOM VIRT DIRECTORY		http://spl-rome.us.org
REPORTS DEFAULT OUTPUT FORMAT		PDF
REPORTS OUTPUT PHYS DIRECTORY		D:\ora10gmid\Apache
REPORTS OUTPUT VIRT DIRECTORY		http://spl-rome.us.org
REPORTS SERVER NAME		repQA1715KAS

Define web configuration settings.

Rule, Option, and Setting

Enter YES or NO in the Option column for each of the rule keys. Also enter the file path or format (as appropriate) in the Setting column.

UPLOAD DIRECTORY - This is the directory where files are stored when they are uploaded to support receiving multiple trackable stock items.

Batch Processes

Check Received PO Item - sdbp_chk_issd_po_item;

Sends an alert to the PO Item Requestor if the PO is fully received. This procedure looks for all issued PO records. For each PO line item with the field Receipts-Fully Received = Y, an Alert will be sent to the Requestor via the home page inbox. If the Requestor is invalid or null, a message will go to the job manager. The field Sent Alert Indicator on the PO Item is set to Y after an Alert/Job Log Message is sent. The Alert will only be sent once.

Invoice Resolution - sdbp_invoice-resolution;

Uses the INVOICE SETUP CRITERIA Business Rule for determining whether mismatched invoice processing is allowed, and tries to resolve mismatched invoices to PO receiving.

Cost Accruals - sdbp_cost_accruals.cost_accruals;

Accrues costs for receiving transactions that have not yet been posted. Information is selected from the table SA_RECEIVING_LOG and posted throughout the system as required.

Code Tables

Code Table 81 - Software Labels (Length = 15)

When a user selects Print Bar Code Labels from the Actions list in the Receiving or Multi-Step Receiving modules the screen below opens. Code Table 81 is only used if the client has purchased the Software Software and wants to print bar code labels. Examples: Tracking Labels, Generic Labels, Receiving Labels.

Examples: Tracking Labels, Generic Labels, Receiving Labels

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Bar Code Print Labels

Grants the ability to print barcode labels from the Multi-Step Receiving record.

Receive More Than Ordered

Grants the ability to receive a greater quantity than what was originally ordered on a purchase order. This functionality is also controlled by the Receiving Configuration business rule. Persons with this responsibility must also have a PIN set up.

Receive All Items As Ordered

Grants access to the Receive All as Ordered Action.

Reports

S_RPT107 - Delivery Receiving Report

Summarizes Purchase Order and Receiving information for selected Receiving sessions.

S_RPT047 - Receipt Delivery Worksheet Report

Lists information regarding items received.

S_RPT025 - Receiving Report

Lists summary Purchase Order and Receiving information for selected Receiving sessions.

S_RPT216 - Receiving Report

Summarizes receiving records by Purchase Order number detailing items received, by whom, receipt date, and other applicable information.

S_RPT037 - Receiving Worksheet Report

Lists items to be received as well as any existing Receiving information.

Multi-Step Receiving Module

Fields

Sequence No.: Delivery ID

The record number is comprised of a unique ID (Ex. "02000006"). Multi-Step Receiving record numbers are typically set to be system generated.

TABLE NAME - SA_DELIVERY - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.


User-Defined

Configure User-Defined fields as needed for your organization. Please refer to the User Guide for more information.

If you use user-defined fields in the Purchase Order module AND you use Multi-Step Receiving, you must make sure that both modules have the same user defined fields.

Business Rules

Alerts Rule



Alert	Recipient
BACKORDERED ITEMS HAVE ARRIVED	REQUESTOR
PARTS HAVE ARRIVED	REQUESTOR
PO ITEM RECEIVED	REQUESTOR
WORK ORDER HAS BEEN APPROVED	REQUESTOR

This business rule identifies system alerts that are available and who should receive the alert. New Alert types cannot be created.

Alert and Recipient

BACKORDERED ITEMS HAVE ARRIVED - Work Orders and Checkout Requests - Enter REQUESTOR in the Recipient column to have an alert sent to the requestor when backordered items come in. The requestor who's Issue Ticket Report has been printed will receive the alert.


PARTS HAVE ARRIVED - Work Order - Enter REQUESTOR or PLANNER in the RECIPIENT column to have an alert sent to the requestor or planner of a work order with a direct purchase is received in the Receiving module. The default is REQUESTOR. When this is set to PLANNER the alert is sent to the planner indicated on the work order task, not on the work order.

PO ITEM RECEIVED - Requisition - Enter REQUESTOR in the PO ITEM RECEIVED column to have an alert sent to the requestor identified on the Requisition when the requested PO item is received.

WORK ORDER HAS BEEN APPROVED - Work Order - Enter REQUESTOR in the RECIPIENT column to have an alert sent to the work order requestor when approval has been processed for the work order.

WO FINISH WITH OPEN PO OR REQ - Purchase Order, Requisition - Enter the person who should receive an alert when a Work Order that references an open purchase order or requisition is set to Finished status. The Default setting is to BOTH.

Bar Code Configuration Rule



Menu Item	Display
CHECKOUTS:RETURNS	ON
LABEL PRINTING	ON
MULTI-STEP RECEIVING	ON
PHYSICAL INVENTORY	ON
RECEIVING	ON
REORDER HANDLING	ON
STOCK TRANSFERS	ON
STOCKING	ON

This rule determines the main menu options available in the RFGen Bar Coding application.

Menu Item and Display

Options set to ON appear on the bar coding main menu.

Barcode Label Printers Rule

Printer Name	Enabled	Quality	Printer No.
4100 INTERMEC	YES	NO	002
4420 INTERMEC	YES	NO	001
4420 INTERMEC Q	YES	YES	001

The Barcode Label Printers Rule defines barcode label printers accessible by the application.

Printer Name

Enter the names of the designated printers.

Enabled

Enter YES or NO to specify whether or not the named printer is enabled.

Quality

Use this field to designate print quality.

Printer No.

Enter the Printer number to print to. Printer numbers are determined by your organization.

Receiving Configuration Rule

Receiving Parameters	Options	Contact Emp.
ADD TAX AT RECEIPT	NO	
BACKORDER PROCESSING CHECK	ON	
RECEIVE MORE THAN ORDERED	YES	

Receiving Parameters and Options

ADD TAX AT RECEIPT - Set this key to YES to have the system calculate the average unit

price for stock items by including invoiced taxes and exchange rates. This calculation reflects the true cost of procurement of the item. When the key is set to NO taxes are not factored into the cost.

BACKORDER PROCESSING CHECK - Enable or disable checking of backordered items in the Receiving, Multi-Step Receiving, and Stock Transfer modules. Set this option to ON if you want the system to prompt the user with a listing of Checkout Requests and Work Orders that require the backordered item when other items on the Purchase Order are received.

RECEIVE MORE THAN ORDERED - This rule key controls whether or not users can receive quantities that exceed the quantity ordered on a purchase order. The setting applies to items received in the Receiving module or the Multi-Step Receiving module. If the key is set to YES (default), quantities greater than the PO item quantity can be received without any warnings or errors being displayed. If the key is set to NO, any attempt to receive quantities greater than the PO item quantity results in an error. If the key is set to RESTRICT, only authorized users can receive quantities that exceed the PO item quantity. Authorization is granted by adding the Receive More Than Ordered function to a user's responsibilities. The Contact Emp. field indicates the person who is primarily responsible for providing authorization to restricted users when needed. The list of values for this list is populated with the name of any user that has the Receive More Than Ordered function in their responsibilities. When the item is received, the system prompts the authorized user for their username and PIN to authorize the receipt.

Vendor Performance Attributes Rule (Shipment Attributes View)

Determine the attributes and associated point values used for vendor performance rating.

Quality Attribute

Enter Quality Attributes that describe the criteria that will be used to determine whether or not a vendor has delivered items or services properly. Typical examples are Packaging, Damage, Delivery, PO Compliance, and Cleanliness.

Point Value

Assign a Point Value, based on the importance of Vendor compliance, to each Attribute.

The system uses the Attributes and Point Values when calculating each Vendor's Performance Rating. The system then used the attributes and points to determine the vendor's overall performance rating.

Batch Processes

Check Received PO Item - sdbp_chk_issd_po_item;

Sends an alert to the PO Item Requestor if the PO is fully received. This procedure looks for all issued PO records. For each PO line item with the field Receipts-Fully Received = Y, an Alert will be sent to the Requestor via the home page inbox. If the Requestor is invalid or null, a message will go to the job manager. The field Sent Alert Indicator on the PO Item is set to Y after an Alert/Job Log Message is sent. The Alert will only be sent once.

Cost Accruals - sdbp_cost_accruals.cost_accruals;

Accrues costs for receiving transactions that have not yet been posted. Information is selected from the table SA_RECEIVING_LOG and posted throughout the system as required.

Invoice Resolution - sdbp_invoice-resolution;

Uses the INVOICE SETUP CRITERIA Business Rule for determining whether mismatched invoice processing is allowed, and tries to resolve mismatched invoices to PO receiving.

Vendor Performance - sdbp_vendor_performance;

Supports the gathering of Vendor Performance statistics. This procedure performs the following:

- Identifies the processing parameters for the Current Rating Period for Active Vendors.
- Updates Quality Performance data based on changes since the last batch run.
- Updates Delivery Performance data for new transactions.
- Updates Quality Performance data for new transactions.


Code Tables

Code Table 57: Container Types (Length = 10)

Container field - Define codes for types of containers that shipments are typically received in. (e.g. Box, Envelope, Pallet).

Code Table 81 - Software Labels (Length = 15)

When a user selects Print Bar Code Labels from the Actions list in the Receiving or Multi-Step Receiving modules the screen below opens. Code Table 81 is only used if the client has purchased the Software and wants to print bar code labels. Examples: Tracking Labels, Generic Labels, Receiving Labels.



Code Table 58: NCM Disposition Codes (Shipment Attributes View) (Length = 20)

NCM Disposition field - Define codes to describe Non-Conforming Materials handling. Some examples of data are: Exchanged, Disposal, Return to Vendor, Repaired/Put on Shelf.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Accept Quality Items

Grants the ability to receive quality items in the Multi-Step Receiving module.

Bar Code Print Labels

Grants the ability to print barcode labels from the Multi-Step Receiving record.

MSR Force PO Complete

Controls whether the Force Complete action is displayed in the MSR item bin block.

Not Vendor Caused

Grants the ability to select the Not Vendor Caused action from the Multi-Step Receiving Actions list. This action prevents vendors from being penalized for a discrepant delivery.

Receive More Than Ordered

Grants the ability to receive a greater quantity than what was originally ordered on a purchase order. This functionality is also controlled by the Receiving Configuration business rule. Persons with this responsibility must also have a PIN set up.

Receive All Items As Ordered

Grants access to the Receive All as Ordered Action.

Reports**S_RPT107 - Delivery Receiving Report**

Summarizes Purchase Order and Receiving information for selected Receiving sessions.

S_RPT047 - Receipt Delivery Worksheet Report

Lists information regarding items received.

S_RPT025 - Receiving Report

Lists summary Purchase Order and Receiving information for selected Receiving sessions.

S_RPT037 - Receiving Worksheet Report

Lists items to be received as well as any existing Receiving information.

S_RPT140 - Completed NCMs

Displays Non-Conforming Material (NCM) shipments that have been completed.



S_RPT216 - Receiving Report

Summarizes receiving records by Purchase Order number detailing items received, by whom, receipt date, and other applicable information.

Material Disposition Module

Business Rules

Reparable Processing Rule



Define options available for reparable processing within the system. These include reparable cost fields on the storeroom, credit for return of items from the checkout module and a separate module for disposition of repairables.

Define options available for reparable processing within the system. These include reparable cost fields on the storeroom, credit for return of items from the checkout module and a separate module for disposition of repairables.

If this rule is missing or an option is not listed, the default is “OFF”.

Option and Option Status

AUTO-POPULATE PNDNG COMPONENT - When this key is ON and the user enters a function, the system generates a list of values of all components in material disposition

status for the Component ID field. If this key is OFF, the system does not generate the list of values and the user must manually enter the Component ID.

Note: The AUTO-POPULATE PENDING COMPONENT rule key is applicable only when ENHANCED MATERIAL DISPOSITION is also set to ON.

ENHANCED MATERIAL DISPOSITION - This turns ON or OFF the special processing associated with the issue and return of repairable components. The default is OFF.

REPAIRABLE MUST BE TRACKABLE - This turns ON or OFF the storeroom validation that a storeroom item CANNOT be repairable unless it is also trackable. The default is OFF.

REPAIRABLE RETURN CREDIT VALUE - This turns ON or OFF the special processing associated with the return of repairable components that are returned USED, but receive a credit and are NOT considered in the on-hand quantity. The default is OFF.

RESTRICT REPAIRABLE CHECKOUT - If this key is set to ON, stock items marked as Repairable can only be checked out against work orders.

When the Enhanced Material Disposition key is set to ON, the Restrict Repairable Checkout key must also be set to ON.

Code Tables

Code Table 59: Material Disposition Repair Types (Length = 10)

Repair Type field - Define classification codes for repairs. This code table can be used in several different ways. Typical examples are: to classify types of repairs or identify who is doing the repair work (e.g. internal or external labor).

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Repair Removed Part

Grants the ability to use the Repair Removed Part Action from the Work Order Task module Actions list to create a Material Disposition record.

Batch Processes

Storeroom Repair Costs - `sdbp_storeroom_repair_costs`;

Sums costs based on the material and account log for material that has been dispositioned from closed work orders.

Managing Advanced Materials

The Material Disposition process was enhanced to allow the tracking of repair costs for non-component Inventory type stock codes that have the Repairable indicator set to "Y" at the storeroom in which the stock code exists in Active status:

Set Up for Advanced Materials Processing Functionality

Repairable Processing Business Rule

The functionality behind this option in the Business Rule was modified in version 5.2 to allow non trackable, but repairable stock items to be included in the Repair Process.

ENHANCED MATERIAL DISPOSITIONSet to ON

REPAIRABLE RETURN CREDIT VALUESet to OFF

REPAIRABLE MUST BE TRACKABLESet to OFF

Component Processing Business Rule

This Business Rule is defaulted to Yes and can only be set to No if the Repairable Processing Business Rule Option ENHANCED MATERIAL DISPOSITION is set to ON. If the INSTALL AT ISSUE option is set to NO, the Material Disposition item will have the initial status of Pending Disposition when issued from the Checkout module. To set the material Disposition status to Installed , you must use the Material Disposition module.

REPAIRABLE RETURN CREDIT VALUESet to No

INSTALL AT ISSUE - Set to No

See Component Processing Business Rule for remaining options.

Physical Inventory Module

Manage inventory counts and adjust quantities as required in the Physical Inventory module.

Business Rules

Bar Code Configuration Rule

Business Rule BAR CODE CONFIGURATION

Rule ID: Configuration Limit?

Desc:

Comment:

Menu Item	Display
CHECKOUTS:RETURNS	ON
LABEL PRINTING	ON
MULTI-STEP RECEIVING	ON
PHYSICAL INVENTORY	ON
RECEIVING	ON
REORDER HANDLING	ON
STOCK TRANSFERS	ON
STOCKING	ON

Description:

This rule determines the main menu options available in the RFGen Bar Coding application.

Menu Item and Display

Options set to ON appear on the bar coding main menu.

Physical Inventory Rules Rule

Business Rule PHYSICAL INVENTORY RULES

Rule ID: Business Limit?

Desc:

Comment:

Physical Inventory Rules	Option Status	True Count Id	True Count Dt
BLIND COUNT	YES		
TRUE COUNT	YES	TC1999-2000	20-MAY-00

Description:

Determine the method of performing Physical Inventory counts used by the system. This Business Rule allows you to select between a standard inventory count and a blind count. The difference involves whether the user is allowed to see the current storeroom's on-hand quantity prior to performing the physical inventory.

Physical Inventory Rule, Option Status, True Count ID, True Count DT

BLIND COUNT - Determines whether or not the Physical Inventory Report should suppress the current inventory quantities.

To perform an inventory count without knowing the system's on-hand quantity, set the OPTION STATUS rule key to YES. Physical Inventory Reports produced for the counters will not contain the system's on-hand quantity for each stock item listed.

To perform standard inventory counts, set the OPTION STATUS rule key to NO. Physical Inventory Reports produced for the counters will contain the system's on-hand quantity for each stock item listed.

This applies to reports S_RPT038, S_RPT104 and S_RPT108.

TRUE COUNT - This rule is only for use with the Advanced Material Management Option.

Physical Inventory Tolerances Rule

Physical Inventory	Tolerance
DOLLAR	100
PERCENT	50
RESULT	WARNING

Determine the dollar and percent tolerances for discrepant inventory counts. When performing a Physical Inventory count, if the counted number of items is different than the inventory quantity currently stored in the system, the system checks this rule to determine if the difference falls within an acceptable dollar and percent tolerance. If a tolerance level is exceeded, the user is prompted, inquiring if a recount is necessary or if the entered value should be accepted.

Physical Inventory and Tolerance

DOLLAR - The storeroom dollar value variance allowed (QUANTITY x UNIT PRICE) in whole dollars.

PERCENT - The percent variance allowed between storeroom dollars value and count value (QUANTITY x UNIT PRICE).

RESULT - Stop and Warning.

Code Tables

Code Table 212: Item Class Codes (Length = 10)

Class field - Classify Stock Items into groups. Typically, Class Codes are set up for high turnover items (to help in generating Physical Inventory lists). Classifying the Stock Items in this manner facilitates searches by allowing queries to be conducted at a high level.

This table is attached to the Class field in the Create List Criteria view.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Adjust Store for Recount

Grants the ability to use the Stores Quantity Wizard from the Physical Inventory Search Options or Search Results screen to process storeroom recounts.

Reports

S_RPT038 - Physical Inventory Listing Report

Lists physical inventories generated sorted by inventory number.

S_RPT039 - Physical Inventory Variance Report

Lists Stock items where the quantity counted is different than the quantity On Hand Quantity maintained within the system. Transactions that took place between the time that the list was first generated and when the count was entered into the system are taken into consideration.

S_RPT104 - Physical Inventory Listing Report

Lists Stock items to be counted as generated from a Physical Inventory. Please see the PHYSICAL INVENTORY Business Rule for more information regarding this report.

S_RPT108 - Inspection/Discrepancy Physical Inventory Report

Lists physical inventories generated sorted by inventory number.

S_RPT109 - Property Inventory - Items Not Found Report

Provides a listing of items not found during an inventory to support physical inventory of property module.

Shipping Memo Module

The Shipping Memo module allows users to manage shipment of materials to outside contractors (Vendors) and account for the return of those items. Typical types of Shipping Memo's are Returns for Credit, Rental Returns, Over shipment, and Miscellaneous Shipments.

Fields

Sequence No.: Shipping Memo No.

The record number is comprised of a unique ID (Ex. "010000003"). Shipping Memo record numbers must be system generated. Manual creation of these record numbers could result in critical system errors when records are created from other records or in batch procedures.

TABLE NAME - SA_SHIPPING_MEMO - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.


System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Business Rules

Shipping Memo Options Rule

Determine whether Shipping Memo records are automatically created from a Requisition and through Receiving or Multi Step Receiving for credit or replacement.



Type	Auto Generate	Type Default
REQUISITIONS	ON	OTHER
RETURNS	ON	RETURN

Description
If this rule key is ON, when the Requisition status is set to APPROVED and Ship Memo Indicator is checked, then a new Shipping Memo record is automatically created by the system (default OFF). The memo type default is OTHER.

Type, Auto Generate, and Type Default

REQUISITIONS - If this rule key is ON, when the Requisition status is set to APPROVED and Ship Memo Indicator is checked, then a new Shipping Memo record is automatically created by the system (default OFF). The memo type default is OTHER.

RETURNS - When this rule key is ON, when Purchase of Direct and Stores items are returned, a new Shipping Memo record is automatically created by the system (default OFF). The memo type default is RETURN.

Copy Record

SHIPMEMO - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Reports

S_RPT210 - Shipping Memo Report

Summarizes Shipping Memo details for reports selected.

Property Management Module

Fields

Sequence No.: Property ID

The record number is comprised of a unique ID. Typically this is user entered.

TABLE NAME - SA_PROPERTY - The sequence number is generated for this database table.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Code Tables

Code Table 53: Property Types (Length = 20)

Type field - Define codes for categories or types of equipment that you want to track by employee. This table is attached to the Type field on the Property module header screen. Some examples of data are: Capital Office (In-Focus, Projectors, Laptops), Car, Communication (Cell Phones, Pagers, Radios)

Code Table 55: Property Classes (Length = 20)

Class field - Define codes to classify or scale different types of property items you want to track by employee. Some examples of data are: High, Low, Medium.

Copy Record

PROPERTY - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Reports

S_RPT110 - Property Inventory - Discrepancies Report

Shows all Property Inventory records with Discrepancies.

S_RPT111 - Property Inventory - Items to be Inventoried Report

Lists items to be inventoried based on the property inventory list created through the Property Inventory module.

S_RPT109 - Property Inventory Report - Items Not Found

Lists items not found during an inventory to support physical inventory of property module.

Consumables Module

Code Tables

Code Table 31: Consumable Types (Length = 6)

Types column - Define codes to identify the type of consumable that is being used. Typical entries include 'Antif' (Antifreeze), 'Oil', 'Ulead' (Unleaded), etc. Note that the maximum data length for this field is set to 6 characters. Identifying Consumable types facilitates searches by allowing queries to be conducted at a high level.

Code Table 32: Consumables Source Codes (Length = 8)

Source column - Define codes to identify the origin of the consumable. Typical entries might be a service station, a garage, etc. Identifying Consumable Source codes facilitates searches by allowing queries to be conducted at a high level.

Customer Subsystem

Customer Module

Fields

Sequence No.: Customer ID

The record number is comprised of a unique ID (Ex. "0000023"). Customer record numbers are typically set to be system generated.

Table Name - SA_CUSTOMER - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Copy Record

CUSTOMER - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Code Tables

Code Table 15: Country Codes

Country Code field - Populate this table with a listing of all Countries that are applicable to your organization. This is a system code table.

Code Table 73: Property Types (Address (Detail) View)

Property Type field - Define codes to identify whether or not the customer is a owner, renter, or holds a lease on the property that is serviced. Examples of data are: Lease, Owner, Renter.

Note: Do not confuse this code table with Code Table 53 which is also called Property Type and relates to the Property Management module.

Service Request Module

Fields

Sequence No.: Service Request No.

The record number is comprised of a unique ID (Ex. "0100005"). Service Request record numbers are typically set to be system generated.

TABLE NAME - SA_SERVICE_REQUEST - The database table that the sequence number is generated for.

Sequence Number, Prefix, and Length - If the system generates the number, you can determine if there is a starting number, what that number should be, and specify a prefix if needed. The length indicates the maximum number of characters that can be used in the number.

System - A check in the System check box indicates that the sequence number should be system generated.

Please refer to [Sequence Numbers Module](#) for more information and examples.

Next Approver Field

Designate approvers for Service Request records in the Approval Limits module of the Administration subsystem under Approvals and Routes.

Business Rules

Expense Codes Rule

Expense Code	Category	Valid Capital	Report Label
00001	Inventory Stock		INVENTORY
00002	Direct Stock		PURCHASE
00007	Leave Expense		MISCELLANEOUS
00010	Direct Charges Exper		
00013	Invoice with PO		

List expense codes and a category for each (such as regular labor, premium labor, stock purchases, direct purchases, etc.).

Expense Code and Category

Enter the valid code (used for accounting) in the EXPENSE CODE column. For each listed code, you can then enter the appropriate category into the CATEGORY column. These codes are used to summarize and categorize costs.

Note: Expense Codes are used with Account numbers to set up budgets for an entity.

CCB Expense

If your organization uses CCB Integration the CCB Expense column defines categories that are used to summarize costs when they are sent to Oracle Utilities Customer Care and Billing from Oracle Utilities Work and Asset Management on the completion of a service request. These codes should correspond to a Characteristic Type in Oracle Utilities Customer Care and Billing. The list of values for this field is defined in code table 1195 - CCB Expense.

Valid Capital

The Valid Capital column is designated for a custom configuration and is not used.

Code Tables

Code Table 240: Service Request Types

Type field - Define codes to identify service request types. Typical entries might be Maintenance, Install, Water, Wastewater, Pipes, or Transmission Line.

Code Table 241: Problem Codes

Problem Code field - Define codes to identify types of problems that could initiate a Service Request. Typical entries might be broken meter, flood, valve, and water main break.

Code Table 242: Deposit and Payment Types (Billing Information View)

Type fields - Define codes to identify ways in which deposits or payments can be made. Some examples of data are: Cash, Check, Money Order, Credit.

Code Table 246: Disconnect Location

Disconnect Location field - Define codes used on the field in the Service Request module Meter Information view.

Code Table 1195 - CCB Expense

If your organization uses CCB Integration, use this table to define codes to use with the Expense Codes business rule.

Code Table 1196 - CCB Install Remove Flag

If your organization uses CCB Integration, use this table to define flag codes.

Copy Record

SERVREQ - COPY RECORD

Add this to users' responsibilities to allow them to copy a record, including header and details, in this module. To display the Copy Record action on the Actions list users must have both the Responsibility and at least one table configured for the module. Please refer to [Modules Administration - Forms Module Copy Record View](#) for more information.

Functions

Add functions to responsibilities to allow users to perform tasks within the system. In most cases, if the function is not enabled, the system will not display the related view or action. The following activities are available when the Ind check box is checked for each function. Please refer to [Responsibility Module Responsibility Types](#) for more information.

Associated Service Request

Grants access to the action that creates an associated service request.

Create WO from Service Request

Allows users to change a Service Request status to work order or to select Create Follow-up Work Order from the Service Request Actions list.

Batch Processes

Cost Service Request -

sdbp_cost_service_request.cost_service_request_rollup

Posts closed service request assets to the cost asset table.

Charts

S_CHT140 - Customer Follow-Up Calls

The number of Service Request follow-up calls made during the current year and the previous year. The data can be filtered further by Plant, Service Request Type and Problem Code.

Metrics

S_MTRC1 - Customer Follow-Up Calls Pending - sdbp_metric_cust_follow_calls

This metric is a count of the total number of Service Requests that are “Ready for Callback.” It provides a means to monitor and improve the efficiency of customer response time.

Reports

S_RPT138 - Service Request Report

Provides a summary of each Service Request selected including work location information, customer information, reported by, and call history.

Chapter 8

Enterprise Subsystem

Executives can view cost enterprise-wide summaries spanning several plants and other organizational units in the Enterprise subsystem. Enterprise data can be used to compare maintenance and inventory costs between different divisions and to locate assets and inventory in other organizational units.

Within the Enterprise subsystem, two additional corporate levels can be identified above Plant. Company is the highest level and can consist of a number of Organizations. Organizations are the second level and can consist of a number of Plants. For each Company, at least one Organization and one Plant must be defined.

Just as Period Cost and Cost Summary information rolls up from Asset to Area to Department within a Plant, Plant Period Cost and Cost Summary information is aggregated at the Company and Organizational levels.

Asset Type Analysis Module

The Asset Type Analysis module provides cost summaries by Asset type for the entire Enterprise and by Plant.

This module is only used to review information, therefore there are no configurable items.

Company Module

Other than establishing Company records, there are no configurable items in this module. The Company ID and description fields are both free form fields where you can define the Company.

Enterprise Asset Module

The Enterprise Asset module is identical to the Asset module in the Resource subsystem, with the addition of Plant as a searchable field. You can search for assets across all plants in your company, or in a particular plant. If you search on some criteria other than plant, you can review the search results to see which plants hold identical or similar assets.

Since this is a replica, all items should be addressed during configuration of the Asset module.

Code Table 75 - 77: Asset Mobile fields 1-3

Asset Code fields - Define codes to use to filter assets when they are downloaded on a PDA.

Enterprise Catalog Module

The Enterprise Catalog module is identical to the Master Catalog module in the Resource

subsystem, with the addition of Plant information on the storeroom summary views.

While you cannot search the Enterprise Catalog module directly for stock items at a particular Plant, you can review the Storeroom Quantity Summary to see what quantities of the item are held in the various Plants identified with your enterprise. Similarly, you can review the Storeroom Reorder Summary to see usage and reordering information from the various Plants.

Since this is a replica, all items should be addressed during configuration of the Master Catalog module.

Organization Module

The second highest level of the enterprise hierarchy is defined in the Organization module. The Organization level can be used for divisions, subsidiaries, brand families, or other grouping that is logical to your enterprise structure.

Once the appropriate organization records have been created and saved, both Company and Organization can be referenced from Plant records.

Other than setting Organization records as children to Company records, there are no configurable items in this module.

Plant Module

Use the Plant module to record and organize information regarding your organization's various work sites.

Fields

Plant

Each plant must have a unique number.

Description

The Description field contains a brief description of the plant.

Company

Select the Company the Plant is identified with from the List of Values. Before a Company can be entered, a corresponding record must exist in the Company module.

Organization

Select the Organization the Plant is identified with from the List of Values. Before an Organization can be entered, a corresponding record must exist in the Organization module for the Company selected.

Locale

The locale field allows you to set the plant location and local language used. These settings affect aspects of the system such as using postal codes rather than zip codes or whether the English or Metric system is used in measurements.

Local Currency and Fiscal Calendar

The Local Currency field is used to establish the default currency code to use on your procurement documents. Currency Codes are defined in the Currency Exchange Rates module of the Administration subsystem.

Together these fields are for use with Business Intelligence functionality. If your organization uses Business Intelligence, these fields must be populated as triggers for

extracting data from Oracle Utilities Work and Asset Management to Business Intelligence. Please see your product representative for more information.

Locale Phone Format

The Locale Phone Format field allows you to set the appropriate formatting for phone number fields. Users enter digits into a phone number field on another record and the system automatically formats the number according to the format set here. This formatting also applies to where phone numbers appear on reports. Select NO FORMATTING to allow free form entry of numbers in any format.

If one phone format is chosen and data is entered, then the format is changed here, the system does not re-format existing data. Please use care and forethought in choosing a phone format. Most US clients will not want to adjust this field from the default.

Include in Run All Batch?

A check in the Include in Run All Batch? check box indicates that the plant will be included in Run All Batch processing. This is important when multiple plants share the same database. If a plant is excluded from Run All Batch processing, each relevant batch process must be run individually for that plant.

Multi-Plant/ Single Plant Usage

The system provides two options for separation of data in the database, the use of multiple Plants or the use of a single Plant with the use of departmental data to separate data. These two configurations offer very different results for customers.

Using Multiple Plants

You only use a Multiple Plant deployment when you want one database instance supporting multiple, separate, discreet deployments of Oracle Utilities Work and Asset Management. This means that everything is duplicated and identified by a Plant column. There is no need for common procurement, common inventory, there is no need for common lookup tables, it is as though there are multiple deployments.

This provides a single database instance and set of application software to be maintained by IT for ALL of your Oracle Utilities Work and Asset Management information so that the IT responsibilities are reduced.

This feature allows you to implement a single database instance to support many versions of the application. This allows your maintenance costs to be greatly reduced having to only support one database from an IT infrastructure perspective. However, the application is structured to keep the information about different plants separated just as though the data was actually stored in difference database instances. Some provisions are made allowing you to search across the various Plants in areas such as Inventory and Assets, but these areas are limited and not pervasive throughout the application. Centralized Inventory or Purchasing is not one of the functions that can easily be implemented in this configuration.

When to Use Multiple Plants

There is a simple question to ask yourself that clarifies the use of a multiple plant deployment.

Would it be correct to deploy the Oracle Utilities Work and Asset Management application to different users in separate database instances on different database servers?

This implies that the multiple deployments would be separate and discreet with no overlap. If you want to search across the instances you would have to bring the data together in a common data warehouse.

There are cases for customers where this makes sense. For example, customers that sell their services to cities and want the deployments at each city to be separate and configured specific for each city. There are no common procurement or codes, so each deployment is unique.

If you answer Yes to this question, then a multiple plant deployment makes sense for the customer and would allow you to implement Oracle Utilities Work and Asset Management in a single database instance on a centralized server.

Separating Data in Oracle Utilities Work and Asset Management

What is often confused with the use of multiple plants is the desire to separate data so that one group of users “do not see” or “can not see” another group of users information. This is common among municipalities that have Water, Waste Water, PW, and Parks & Recreation departments. This is an entirely different question and a multi-plant deployment does not solve this issue.

There are other Oracle Utilities Work and Asset Management features that help meet this request like Fine Grain Access which allows for Virtual Private Databases. There are also many configuration features that allow you to default search criteria that keep users in a specific “funnel” of data by default but that allow you to search across departments when necessary.

Single Plant - Multiple Departments

This configuration allows you to implement a centralized inventory and/or purchasing process that can support the various departments. This basic configuration of the application should not require any unique software to be developed. The application is designed to provide real-time integration between the various work management departments, inventory management and purchasing. However, there are often concerns about creating a centralized open view of information in an application such as this one. If your organization has various departments that may have different ways of doing business and may be concerned about having to “live by” another departments business rules. For example, a Parks department may not have the same processes in place as a Wastewater Treatment Plant and those departments may be different than a Fleet operation. We have found that there are often many similarities in the way work is managed in various departments and for the most part there are few conflicts. In the few places where business practices may differ, the Oracle Utilities Work and Asset Management team works with the departments to develop a solution that works for each department. We provide a variety of ways to allow you to configure the application to meet these special requirements.

Additional Considerations

Some of the issues that arise when we work through a multiple departmental installations, include:

- Business Rule Settings - What if they need to be different for the different departments?
- Asset Hierarchy - Do the various departments have to have the same Asset structures?
- Data Availability - Can each department see each others information?

Business Rules

The business rules, are by default, common to each user in the single plant configuration. We have found that the rules are often easily agreed upon by the various departments and are also often departmentally exclusive. For example, setting a business rule in the fleet work order system will not affect the work order processing for the plant.

Asset Hierarchy

The asset hierarchy is a valuable feature that is very useful to our customers. Since this feature is a data model and not a process built into the application, you are not required to have the same hierarchy for each department.

Data Availability

This concept is related to the viewing of information within modules. The base security within the system is related to the module. Users are given responsibilities to select, insert, update, or delete records in modules. For example, if you have access to view work orders, you are able to view all work orders in all departments. This is sometimes viewed as a problem by departments, in the form of the Parks department does not want Communications to see their work orders. If this issue arises, there are several system features that you can use to help ease concerns.

One useful feature is the ability to set up defaults on search options screens to allow configuration of “vertical data segments” within a module. For example, you may set up a user to default the department PARKS on each search options screen. This default is saved as part of the user profile and remembered each time you enter the module. This has the affect of keeping a user in a segment of data within a module by default. The user is able to override the defaults, but would have to consciously modify his or her settings to see data from other departmental setting search defaults is not sufficient and there is a need to more formally secure the data within a module, the system also includes a feature called Fine Grain Access (FGA). FGA utilizes a database concept called “virtual private databases” allowing you to set security on a set of data within a module or table. Each user can be included or excluded from viewing specific records in each module. FGA relies on a database construct called a “database policy”. Access to the rows in the table is controlled at the database level, not by the application. This means that the “database policy” keeps data hidden from the user regardless of how the table is being accessed. The default access may certainly be through the module, but if the user were to run a report or use a third party tool, where they log on as the same user, the data will remain “hidden” to them.

If fine grain access is used, you will not be able to view data across departments, even in search mode, unless you create a second user with access to this data, and then sign on as the new user. This feature also requires that the Oracle database be Oracle Enterprise Edition. Database Policies are not available in Oracle RDBMS Standard Edition.

Index

A

ABC Inventory Business Rule	
Storeroom Setup Module	150
Account Creation from Projects Business Rule	
Project Module	322
Account Distribution Template Module	139
Account Module	133
Account Period Override Rule	
Accounting Periods Module	128
Account Rules (Custom)	80
Account Structure Module	126
Accounting Periods Module	128
Activities Requiring an Approval Title	
Approved Vendor Override	74
Discrepancy Activity	74
Discrepancy Owner	74
Inspection Owner	74
Material Planner	74
Physical Inventory Wizard	74
Timesheet Wizard	74
Activity Tracking Module	279
Actual Cost to Planning Estimate	256
Advanced Materials Management Option (AMMO)	84, 91
Alerts	
Approval Alerts	75
Auto Stock Reorder	439
Backordered Items Arrived	247, 369, 378, 423, 435, 443, 449
Budget Overage	135
Default E-Mail Address For	43
Issue Qty. Exceeds WO Estimate	44, 432
Multiple Blanket Contract Revisions	393
Out of Range Asset Data	178
Parts Arrived	247, 369, 378, 423, 435, 443, 449
PO Fully Received	387
PO Item Received	247, 369, 378, 423, 435, 443, 449
Project Exceeds % Tolerance	323
Project Exceeds Budget Tolerance	323
System-Wide Settings	44
Alerts Business Rule	
Checkout Request Module	423
Multi-Step Receiving Module	449
Purchase Order Module	378
Receiving Module	443
Requisition Module	369
Stock Transfer Module	435
Work Order Module	247
Allow Duplicate View	
Modules Administration - Forms Modules	104
Ammo Related Business Rules	84
AMMO Related Code Tables	91
Analysis Views Access List (Custom)	80
AP Batch Interface (Custom)	80
AP Batch Interface Business Rule (Custom)	80
Approval Limit Module	73
Approval Route	75
Approval Route Field	
subproject module	321
Approval Routing Business Rule	
Routing List Module	75
Approvals	73
Approval Route Field	
asset module	157
change order module	390
direct charges module	339
invoicing module	402
permit module	296
project module	321
purchase order module	377
requisition module	368
work design module	241
work request module	231
Modules Requiring Approval Title	74
Next Approver Field	
change request module	196
cost adjustment module	414
request for quotes module	398

service request module	467	Attachment Printing Business Rule	
timekeeping module	346	Permits Module	298
Special Considerations		Attachment Types Business Rule	
account default	133	Attachment Modules	206
approval types	88	Audit Log	
approve all timesheets	357	Transaction Logs	53
auto approve change orders	390	Authentication	57
auto invoice approver	145	Auto Generate Daily Schedule Business Rule	
blanket contract approvers	394	Crew Module	275
process defaults	227	Daily Schedule Module	331
project/subproject defaults	323	Auto Generate Weekly Schedule Business Rule	
purchase order	86	Workweek Schedule Module	335
receiving	445	Available Quantity Calculation Business Rule	
reorder review	439	Storeroom Module	143
resend approval request	375		
route timesheets for approval	357	B	
timekeeping authority	351	Backorder	247, 369, 378, 386, 423, 435, 443, 450
use asterisk	40	Bar Code Configuration Business Rule	
work request defaults	238	Checkout Request Module	424
Approved	323	Multi-Step Receiving Module	450
Area Module	132	Physical Inventory Module	458
Asset Activity Log Module	169	Receiving Module	444
Asset Class Module	171	Stock Transfer Module	435, 436
Asset Data Module	179	Storeroom Stocking Module	438
Asset Depreciation Accounts View		Barcode Label Printers Business Rule	
Asset Module	165	Multi-Step Receiving Module	451
Asset Depreciation Business Rule		Receiving Module	444
Asset Class Module	171	Barcode Label Printers Business Rule (Obsolete)	84
Asset Module	160	Barcoding Checkout Business Rule	
Fleet Asset Module	281	Stock Checkout Module	431
Asset Inspection Data Module	176	Batch Job Control Business Rule (General)	63
Asset Interfaces View		Batch Job Control Processes	
Asset Module	165	sdbp_auto_create_timesheet.main	66
Asset Key Segments Business Rule		sdbp_blanket_services.auto_activate	66
Asset Module	161	sdbp_blanket_services.auto_close	66
Fleet Asset Module	282	sdbp_check_lot_expiration	66
Asset Module	157	sdbp_check_pick_queue	66
Asset Navigator Business Rule		sdbp_chk_issd_po_item	66
Home Page	37	sdbp_clean_user_n_user_profile	70
Asset PM Control Module	316	sdbp_close_work_orders.close_work_orders	66
Asset Runtime Rule		sdbp_cost_accruals.cost_accruals	66
Asset Module	158	sdbp_cost_adjustment	66
Runtime Entry Module	330	sdbp_cost_asset.cost_asset	67
Asset Type Analysis Module	470	sdbp_cost_invoice.cost_invoice	67
Assigned Users View	96	sdbp_cost_labor.cost_labor	67
Associate Permit Requirements View		sdbp_cost_service_invoice.cost_service_invoice	67
Asset Module	165	sdbp_cost_service_request.cost_service_request_rollup	67
Attachment Drive Mapping Business Rule			
Attachment Modules	206		
Purchase Order Module	392		
Attachment Print Configuration Business Rule			
Attachment Modules	205		

sdbp_cost_stock.cost_stock	67	sdbp_cost_adjustment	66
sdbp_create_bom_details.create_bom_details	67	sdbp_cost_asset.cost_asset	67, 164
sdbp_default_accounts_status	66	sdbp_cost_invoice.cost_invoice	67, 147
sdbp_direct_charges.direct_charges	67	sdbp_cost_labor.cost_labor	67
sdbp_end_period_depreciation	67	sdbp_cost_route.cost_route	71
sdbp_event_queue.clear_events	66	sdbp_cost_service_invoice.cost_service_invoice	67
sdbp_finish_wo	67	sdbp_cost_service_request.cost_service_request_rollup	67
sdbp_generate_all_chart_images	68	sdbp_cost_stock.cost_stock	67, 147
sdbp_held_for_parts	68	sdbp_create_bom_details.create_bom_details ...	67, 155, 164,
sdbp_invoice_resolution.resolve_invoices	68		195
sdbp_metric_handler	68	sdbp_create_change_req.create_change_from_wo	.198
sdbp_pay_voucher.pay_voucher	68	sdbp_create_new_leave_year.new_leave_year	71
sdbp_pm_cycle_job.start_job	68	sdbp_default_accounts_status	66
sdbp_pm_finish	68	sdbp_direct_charges.direct_charges	67
sdbp_pm_routing	68	sdbp_end_of_period_processing	71, 147
sdbp_po_closeout	68	sdbp_end_period_depreciation	67, 164, 285
sdbp_post_leave	68	sdbp_ers_invoicing	71
sdbp_post_timesheets.post_time	68	sdbp_event_queue.clear_events	66
sdbp_process_service_timesheet.accumulate_posted	66	sdbp_finish_wo	67
sdbp_process_service_timesheet.post_approved_time	69	sdbp_generate_all_chart_images	68, 108
sdbp_process_warranty_alerts	70	sdbp_generate_chart_image	71, 108
sdbp_project_alert.alert_job	69	sdbp_held_for_parts	68
sdbp_purge_data	69	sdbp_invoice_resolution.resolve_invoices	68
sdbp_purge_requisitions.purge_req	69	sdbp_job_error_log	71
sdbp_purge_work_order.purge_wo	69	sdbp_materialized_view	36
sdbp_purge_work_requests.purge_wr	69	sdbp_metric_handler	68, 108
sdbp_regulatory_account_cost	69	sdbp_metric_pct_plan_outage	164
sdbp_reschedule.job_reschedule	69	sdbp_pay_voucher.pay_voucher	68
sdbp_stock_reorder.stock_reorder	70	sdbp_pm_cycle_job.start_job	68
sdbp_storeroom_demand	69	sdbp_pm_finish	68
sdbp_storeroom_on_order	70	sdbp_pm_routing	68
sdbp_update_tmpl_status	70	sdbp_po_closeout	68
sdbp_vendor_performance.vendor_performance	70	sdbp_post_leave	68
sdbp_work_order.fixed_asset	68, 69	sdbp_post_timesheets.post_time	68
sdbp_year_end_oh_cost_dist	70	sdbp_process_service_timesheet.accumulate_posted	.66
smu_interface.sdbp_mu_interface	66	sdbp_process_service_timesheet.post_approved_time	69
Batch Processes	66	sdbp_process_warranty_alerts	70
debugging	72	sdbp_project_alert.alert_job	69
Batch Processes (by procedure)		sdbp_purge_data	62
sdbp_auto_create_timesheet.main	66, 203	sdbp_purge_requisitions.purge_req	69
sdbp_blanket_services.auto_activate	66	sdbp_purge_work_order.purge_wo	69
sdbp_blanket_services.auto_close	66	sdbp_purge_work_requests.purge_wr	69
sdbp_check_lot_expiration	66	sdbp_regulatory_account_cost	69, 142
sdbp_check_pick_queue	66	sdbp_req_template_status_chk	71
sdbp_chk_issd_po_item	66	sdbp_reschedule.job_reschedule	69
sdbp_clean_user_n_user_profile	70	sdbp_run_all_batch	62, 71
sdbp_close_work_orders.close_work_orders	66	sdbp_stock_reorder.stock_reorder	70, 148
sdbp_cost_accruals.cost_accruals	66		

sdbp_storeroom_demand	69, 147, 148	Leave Request	68, 344, 358
sdbp_storeroom_on_order	70, 148	Metric Handler	68, 108
sdbp_storeroom_repair_costs	71, 148	Payroll Voucher	68, 345
sdbp_update_tmpl_status	70	PM Cycle	68, 252, 273, 309, 315, 333, 337
sdbp_vendor_performance	70	PM Finish	68, 253, 309
sdbp_work_order.fixed_asset	68, 69, 142	PM Routing	68, 309, 320
sdbp_year_end_oh_cost_dist	70, 142	PO Closeout	68, 387
smu_interface.sdbp_mu_interface	66	Post Timesheet	68, 358
Batch Processes (by process name)		Process Fixed Assets	69, 142, 271
Account Distribution Template	66	Process Service Timesheet	69, 252, 271, 315, 422
Accumulate Posted Service Invoices	66	Project Alert	69, 328
Accumulate Posted Service Timesheets	420	Purge Data	62, 69
Asset Cost Allocation	415	Purge Requisitions	69, 376, 387
Asset Depreciation	67, 164, 285	Purge Work Order	69, 253
Auto Activate Blankets	66, 397	Purge Work Requests	69, 238, 253
Auto Close Blankets	66, 397	Refresh Materialized View(s)	36
Auto Create Timesheets	66, 203	Regulatory Account Cost	69, 142, 272
Auto Invoicing	409	Requisition Template Status Check	376
Automatic Invoicing	71	Reschedule Work	69, 271, 333, 337
Check Lot Expiration	66	Reset Demand Quantity	69, 147, 253, 271, 315
Check Pick Queue	66	Reset On Order Quantity	70, 148
Check Received PO Item	66, 387, 447, 452	Run All Batch	62, 71
Clear Event Queue	66	Stock Reorder	70, 148, 442
Close Work Order	66, 252	Storeroom Demand	148
Cost Accruals	66, 447, 452	Storeroom Repair Costs	71, 148, 456
Cost Adjustment	66, 415	Synchronize User	70, 121
Cost Adjustment for PM Route	71, 271, 319, 415	Update Template Status	70
Cost and Closeout	66, 271, 341, 358	Vendor Performance	70, 366, 387, 453
Cost Asset	67, 164, 270	Warranty Expiration Alerts	70, 411, 413
Cost Invoice	67, 147, 409	Work Order Labor	272, 273
Cost Labor	67, 271	Year End OH Distribution	70
Cost Service Invoice	67	Year End Overhead Distribution	70, 142
Cost Service Invoice (by process name)	420	Batch Purge Criteria Business Rule	
Cost Service Request	67, 469	Home Page	64
Cost Stock	67, 147	Purchase Order Module	379
Create BOM Details	67, 155, 164, 195	Requisition Module	370
Create Change Request	271	Work Order Module	247, 248
Create New Leave Year	71, 344	Work Request Module	232
Direct Charges	67, 340	Batch Purge Parameters Business Rule	
End of Period Processing	71, 147	Home Page	65
End Period Depreciation	67	Purchase Order Module	380
Finish WO	67, 253, 271	Requisition Module	371
Fixed Asset Valuation	68	Work Order Module	249
Generate All Chart Images	68, 108	Work Request Module	233
Generate Charts	71, 108	Batch Stock Reorder Business Rule	
Held for Parts	68, 252, 271	Reorder Review Module	439
Invoice Resolution	68, 409, 447, 452		
Job Manager	62		

Benchmark Work Order Module	273	Budget Checking	134
Bill of Materials Module	194	Budget Checking by Document	135
Bin Quantity Tracking Options Business Rule (AMMO)	84	Budget Checking Skip Accounts	136
Blanket Contract Access List Business Rule		C.O. Auto Approve Percentage	390
Blanket Contract Module	394	Catalog Interface	83
Blanket Contract Module	392	Change Request Record Types	197
Blanket Contract Processing Business Rule		Charts and Metrics Settings	109
Blanket Contract Module	393	Checkout Allowable Charge Type	430
Blanket Contract Report	397	Checkout Processing	430
Budget Checking Business Rule		Checkout Request	424
Account Module	134	Compatible Unit Defaults	190
Budget Checking By Document Business Rule		Compatible Unit Function	191, 242
Account Module	135	Component ID Rule	181
Budget Checking Skip Accounts Business Rule		Component Processing	182
Account Module	136	Copy/Paste Object IDs	37
Business Rules		Cost Adjustments	414
ABC Inventory	150	Craft Rates	201, 276, 346
Account Creation from Projects	322	Credit Card Purchases	258, 372, 381
Account Interface	83	Criticality Override	158, 234, 258
Account Period Override	128	Customer Address Interface	83
Account Rules	80	Customer Interface	83
Accrual Interface	83	Customer SA Interface	83
Alerts	247, 369, 378, 423, 435, 443, 449	Default Accts for Interfaces	83
Analysis Views Access List	80	Default Backlog Groups	234, 259, 306, 332, 336
AP Batch Interface	80	Default Directories	38, 179, 183, 398, 444
Approval Routing	75	Default File Locations	39
Asset Depreciation	160, 171, 281	Default Work Request Req Date	235
Asset Interface	83	Direct Charge Types	340
Asset Key Segments	161, 282	Do Approvals Query	40
Asset Navigator	37	Do Attachments Query	40
Asset Runtime	158, 330	Do Notes Query	40
Attachment Drive Mapping	206	Document Storage Types	207
Attachment Print Configuration	205	Downtime Type by Work Type	283
Attachment Printing	298	Drilldown Configuration	41
Attachment Types	206	EDI Transaction Codes	80
Auto Generate Daily Schedule	275, 331	E-Mail Configuration	43
Auto Generate Weekly Schedule	335	Employee Interface	83
Available Quantity Calculation	143	End of Period Processing	129
Bar Code Configuration	424, 435, 438, 444, 450, 458	Enforce Receiver	445
Barcode Label Printers	444, 451	Expense Codes	136, 467
Barcoding Checkout	431	Federal Tax Rebate	402
Batch Job Control	63	Fleet Constants	283
Batch Purge Criteria	64, 232, 247, 248, 370, 379, 392	Fleet Mileage Reasonability	284
Batch Purge Parameters	65, 233, 249, 371, 380	GIS Asset Interface	80
Batch Stock Reorder	439	GIS Setup	81
Bin Quantity Tracking Options	84	GIS View Attributes	81
Blanket Contract Access List	394	GL Transaction Interface	83
Blanket Contract Processing	393	Home Page Component Alias	41

Inspection Report Generation	84	Project Management	325
Interface Parameters	84	Project Work Order Account	326
Interfaces	81, 83	Purchasing Options	373, 384, 391, 395, 408
Internal Tracking Options	84	Quote Options	84
Invoice Prorate Defaults	405	Receiving Configuration	436, 445, 451
Invoice Setup Criteria	144, 403	Regulatory Account Options	141
Invoice Tolerances	406	Regulatory Account Usage Codes	140
Labor Burden Multipliers	347	Regulatory Acct Overhead Class	141
Labor Costing Markups	348	Repairable Processing	455
Labor Costing Wage Rates	348	Report Labels	81
Manufacturer Vendor Interface	83	Requisition to PO Rule	372
MDI Window Title	41, 42	Restrict List of Values	47
Multiple Active Contracts	393	RFGen Barcoding Setup	81
Optional Message Presentation	44, 432	S_RPT071 Crew Craft Columns	251
Oracle CAI Financials Admin	81	SAIF Charge Numbers Interface	81
Oracle Financials	81	Scheduled Holidays	201
Oracle Purchasing	81	Scheduling Options	333
OUBI Setup	81	Serv Invoice Account Override	418
Overtime Standings	349	Serv Invoice Prorate Defaults	419
Password Security	119	Serv Invoice Tolerances	420
Payment Terms	361, 407	Service Request Interface	83
Payroll Voucher Types	345	Service Timesheet Charge Types	421
Permit Processing	298	Shelf Life	153
Permit Type	297, 302	Shift Differential Rates	350
Physical Inventory Rules	458	Shipping Memo Options	461
Physical Inventory Tolerances	459	Specification Upload Defaults	184, 446
PIN Processing Administration	45	Spell Check	48
Planner	159, 228, 236, 250, 259, 284	Standard Service Req Interface	82
PM Fleet Types	317	Storeroom Demand Allocation	146, 426
PM Master Parameters	306	Storeroom Interface	83
PM Route Options	260, 319	Stores Transaction Groups	84
PM Schedule Basis	308	Timekeeping Authority	202, 342, 351
PM Seasonal Adjustments	309	Timekeeping Charge Types	352
PO Aging Rules	381	Timekeeping Comp Time Request	353
PO Report Constants	242, 382	Timekeeping Copy Options	353
PO Report Status Codes	383	Timekeeping DTA Pay Code	81
Primary Menu	46	Timekeeping DTA Regular Type	81
Printer Alias	120, 207	Timekeeping Editchecks	354
Procedure Attachment Update	222	Timekeeping Labor Earning Type	354
Procedures Authority	223	Timekeeping Leave Types	343
Procurement Level	152	UDFs- Auto Copy Across Modules	49
Product Int CCB Contacts	82	Unit of Measurement	50
Product Int CCB FA Types	82	Update Primary Vendor	153
Product Integration	82	Validate Task Report Codes	261
Product Integration CCB	82	Variable Expense Codes	261, 356, 427, 432
Product Integration CCB Status	82	Vendor Interface	83
Product Integration Field Work	82	Vendor Options	362
Project Budget Options	323	Vendor Performance Attributes	363, 452

Vendor Performance Ranges	364, 399
Warranty Processing	412
Web Configuration	111, 184, 208, 447
Web Services Gateway	82
WO Aging	251
WO Processing	251
Work Design Phase	243
Work Design Processing	243
Work Order Processing	198, 263, 327
Work Order Task Planning	267
Work Order Travel Time	267
Work Priority Defaults	252
Work Request Authority	236
Work Request Processing	238
Work Week	332, 333, 336, 338
Business Rules Module	79
Buyers Module	86

C

C.O. Auto Approve Percentage Business Rule	
Change Order Module	390
Cache	
clear	56
Change Order Module	390
Change Request Module	196
Change Request Record Types Business Rule	
Change Request Module	197
Charts	106
Actual Cost to Planning Estimate	256
Corrective vs. Preventive Work Orders	256
Customer Follow-Up Calls	469
Departmental Costs Summary	132
disabling thumbnails	110
Emergency Work Orders	256
iis server settings	106
in Office 2007	107
Inventory Turns	148, 155
Inventory Valuation	148, 155
Late PMs for Safety Equipment	310
Late Preventive Maintenance Work Orders	310
Planned Vs. Unplanned Downtime	164, 169
Planning Accuracy	256
PM Forecast Months	311
PM Forecast Months - Estimated Duration	311
PM Forecast Weeks	311
PM Forecast Weeks - Estimated Duration	311
PM History Months	311
PM History Weeks	311

PO By Buyer - Count of POs	387
PO By Buyer - Total Amount	387
PO By Vendor - Count of POs	366, 387
PO By Vendor - Total Amount	366, 387
Preventive Maintenance Investment	256, 311
Preventive Work Orders	311
Project Analysis	328
Timekeeping Analysis	358
Work Order Aging	256
Charts and Metrics Settings Business Rule	
Work Order Module	109
Checkout Allowable Charge Type Rule	
Stock Checkout Module	430
Checkout Processing Business Rule	
Stock Checkout Module	430
Checkout Request Business Rule	
Checkout Request Module	424
Checkout Request Module	423
Chemical Label Module	217
Code Table and Codes Module	87
Code Tables	
0 - Yes/No (System)	88
1 - Work Order Types (System)	88
2 - Maintenance Classes	
Fleet Work Order Module	288
Work Order Module	253, 315
Work Request Module	239
3 - Maintenance Categories	
Fleet Work Order Module	288
Work Order Module	253
Work Request Module	239
4 - Storeroom Types	
Storeroom Setup Module	150
5 - Permit Types (Obsolete)	91
6 - Hazardous Types	
Master Catalog Module	154
7 - Deliver to Location	
Checkout Request Module	428
Purchase Order Module	385
Requisition Module	375
8 - Permit Cancel Codes	
Permits Module	296
9 - Repair Codes	
Work Order Task Module	268
10 - Failure Codes	
Work Order Task Module	269
Work Request Module	238
11 - Vehicle Class (Obsolete)	91
12 - Shop Codes	
Fleet Asset Module	286
Fleet Work Order Module	288
Work Order Module Task	267

13 - Type of Activity Activity Tracking Module	279	37 - Specification Types Specification Template Module	218
14 - Type of Activity Units Activity Tracking Module	279	38 - Drive Types Fleet Asset Module	285
15 - Country Codes (System)	88	39 - Fuel Types Fleet Asset Module	285
16 - Procedure Types Procedure Module	221	40 - Criticality Codes Asset Module	162
17 - Issue Methods Request for Quotes Module	400	Fleet Asset Module	285
18 - Purchasing Commodity Codes Master Catalog Module	154	Work Request Module	239
19 - PM Frequency Codes (System)	88	41 - Work Priority Codes Fleet Work Order Module	288
20 - PM Route Types PM Route Module	319	Work Order Module	253
21 - Printer Names for Reports (Obsolete)	91	Work Order Module Task	268
22 - Vendor Characteristic Types Compatible Units Module	188	Work Request Module	239
Vendor Module	364	42 - Lube Methods PM Route Module	319
Work Design Module	243	43 - FOB Purchase Order Module	386
23 - Units of Measure Asset Inspection Data Module	176	Requisition Module	375
Compatible Structure	186	Vendor Module	364
Compatible Units	189	24 - Rental Types Reservations/Motorpool Module	292
Master Catalog Module	154	25 - Building Codes Asset Module	161
Purchase Order Module	386	Fleet Asset Module	286
Requisition Module	375	Process Module	227
24 - Rental Types Reservations/Motorpool Module	292	Tag Point Module	301
25 - Building Codes Asset Module	161	Work Request Module	239
Fleet Asset Module	286	26 - End Use Codes Purchase Order Module	386
Process Module	227	Requisition Module	375
Tag Point Module	301	27 - Work Codes (Obsolete)	91
Work Request Module	239	28 - Procedure Categories Procedure Module	221
26 - End Use Codes Purchase Order Module	386	29 - Asset Types Asset Module	162
Requisition Module	375	Bill of Materials Module	194
27 - Work Codes (Obsolete)	91	Procedure Module	221
28 - Procedure Categories Procedure Module	221	30 - Runtime (System)	88
29 - Asset Types Asset Module	162	36 - Consumables Category (System)	88
Bill of Materials Module	194	31 - Consumable Types Consumables Module	464
Procedure Module	221	32 - Consumables Source Codes Consumables Module	464
30 - Runtime (System)	88	33 - Blanket PO Types (Obsolete)	91
36 - Consumables Category (System)	88	34 - State or Province (System)	88
31 - Consumable Types Consumables Module	464	35 - Category Codes (System)	88
32 - Consumables Source Codes Consumables Module	464	Blanket Contract Module	396
33 - Blanket PO Types (Obsolete)	91	Service Contracts Module	417
34 - State or Province (System)	88	37 - Specification Types Specification Template Module	218
35 - Category Codes (System)	88	38 - Drive Types Fleet Asset Module	285
Blanket Contract Module	396	39 - Fuel Types Fleet Asset Module	285
Service Contracts Module	417	40 - Criticality Codes Asset Module	162
37 - Specification Types Specification Template Module	218	Fleet Asset Module	285
38 - Drive Types Fleet Asset Module	285	Work Request Module	239
39 - Fuel Types Fleet Asset Module	285	41 - Work Priority Codes Fleet Work Order Module	288
40 - Criticality Codes Asset Module	162	Work Order Module	253
Fleet Asset Module	285	Work Order Module Task	268
Work Request Module	239	Work Request Module	239
41 - Work Priority Codes Fleet Work Order Module	288	42 - Lube Methods PM Route Module	319
Work Order Module	253	43 - FOB Purchase Order Module	386
Work Order Module Task	268	Requisition Module	375
Work Request Module	239	Vendor Module	364
42 - Lube Methods PM Route Module	319	44 - Lube Types PM Route Module	319
43 - FOB Purchase Order Module	386	45 - Training Courses Employee Module Training View	203
Requisition Module	375	46 - Payroll Group Employee Module	203
Vendor Module	364	47 - Service Contract Rate Types (Obsolete)	91
44 - Lube Types PM Route Module	319	48 - Leave Reason Codes Employee Module	203
45 - Training Courses Employee Module Training View	203	Leave Request Module	344
46 - Payroll Group Employee Module	203	49 - PM Route Task Types PM Route Module	319
47 - Service Contract Rate Types (Obsolete)	91	50 - Duration Units (System)	88
48 - Leave Reason Codes Employee Module	203	51 - Failure Modes Work Order Task Module	269
Leave Request Module	344	52 - Root Cause Codes Work Order Task Module	269
49 - PM Route Task Types PM Route Module	319	53 - Property Types Property Management Module	463
50 - Duration Units (System)	88	54 - Note Types	50
51 - Failure Modes Work Order Task Module	269	55 - Property Classes Property Management Module	463
52 - Root Cause Codes Work Order Task Module	269	56 - Vendor Characteristics Vendor Module	364
53 - Property Types Property Management Module	463	57 - Container Types Multi-Step Receiving Module	453
54 - Note Types	50	58 - NCM Disposition Codes Multi-Step Receiving Module	453
55 - Property Classes Property Management Module	463	59 - Material Disposition Repair Types Material Disposition Module	456
56 - Vendor Characteristics Vendor Module	364	60 - Duration Units (System)	88
57 - Container Types Multi-Step Receiving Module	453	61 - Sources Type for Isolation Asset Module	162
58 - NCM Disposition Codes Multi-Step Receiving Module	453	Tag Point Module	301
59 - Material Disposition Repair Types Material Disposition Module	456		
60 - Duration Units (System)	88		
61 - Sources Type for Isolation Asset Module	162		
Tag Point Module	301		

62 - Required Position for Isolation Asset Module	162	102 - Specification Types Specification Template Module	218
63 - Tag Types Component ID Module	181, 186	103 - Req'd Documentation Types (Obsolete)	91
64 - Form Function Types (System)	88	105 - Specification Categories for Assets Asset Module	162
65 - Purchasing Vendor Characteristics (System)	88, 365	107 - Meter Units Asset Class Module	172
66 - Approval Types (System)	88	Asset Module	162
67 - Vehicle Make Fleet Asset Module	286	Fleet Work Order Module	288
Fleet PM Control Module	316	PM Master Module	305
68 - Vendor Classification Types Vendor Module	364	Runtime Entry Module	330
69 - Reorder Reviewer Code Storeroom Module	146	Work Order Task Module	268
70 - Measurement Type Operational Tolerance Module	178	108 - Event Groups PM Event Module	313
71 - Work Types for BI Integration (System)	88	PM Master Module	305
72 - Timesheet Reg Time Types (Obsolete)	91	109 - Event Types PM Event Module	313
73 - Property Types Customer Module	465	PM Master Module	305
74 - Street Directions (System)	88	110 - Backlog Groups Asset Module	162
75 - Asset Mobile Filters Asset Module	162	Crew Activity Log Module	278
Enterprise Asset Module	470	Function Module	226
76 - Asset Mobile Filters Asset Module	162	Process Module	227
Enterprise Asset Module	470	Work Order Module	253
77 - Asset Mobile Filters Asset Module	162	Work Request Module	239
Enterprise Asset Module	470	111 - Overtime Crew Employee Module	203
79 - Phys True Count Item Status (System)	88	112 - Overtime Zone Employee Module	204
81 - Loftware Labels Multi-Step Receiving Module	453	115 - Auditor Codes Vendor Module	365
Receiving Module	447	120 - Crew Event Types Crew Activity Log Module	278
90 - Project Types (Obsolete)	91	Work Order Activity Log	254
91 - Standard Note Types Standard Notes Module	220	121 - Purchasing Event Types Purchasing Log Module	416
92 - Invoice Item Types (Obsolete)	91	122 - Commodity Category Codes Master Catalog Module	154
93 - Report Output File Formats (System)	88	Vendor Module	364
94 - Report Called By Modules (System)	88	123 - Commodity Composition Master Catalog Module	154
95 - Rpt Slctn Block File Locations (DBA)	90	Vendor Module	365
96 - Report Group (DBA)	90	124 - Commodity Composition Master Catalog Module	154, 365
97 - Report Types (DBA)	90	125 - Commodity Composition Master Catalog Module	154, 365
98 - Administrative Department Employee Module	203	128 - Commodity Composition Master Catalog Module	154, 365
99 - Classification Employee Module	203	129 - Commodity Composition Master Catalog Module	154, 365
10 - Failure Codes FMEA Template Module	315	130 - Asset Interface Types Asset Module	162
100 - Checkout Request Priority Checkout Request Module	428	133 - Eng Spec Linked Codes (Obsolete)	91
101 - Specification Types Specification Template Module	218	135 - Assigned Planner (Obsolete)	91
		136 - Create New Asset Transaction Types Change Request Module	196

137 - Function Types Function Module	226	168 - Justification Types Change Request Module	196
138 - Process Types Process Module	227	173 - Vendor Capability Vendor Module	365
139 - Downtime Codes Work Request Module	239	174 - Vendor Capability Vendor Module	365
140 - Return Problem Codes (AMMO)	91	175 - Vendor Evaluation Grades Vendor Module	365
141 - Change Asset Information Transaction Types Change Request Module	196	176 - Expense Report Category (Obsolete)	91
142 - Tracking Transaction Codes (System)	88	177 - Vendor Capability Vendor Module	365
143 - Receiving Transaction Codes (System)	88	178 - Vendor Capability Vendor Module	365
144 - Inventory Transaction Codes (System)	88	179 - Vendor Capability Vendor Module	365
145 - Stores Transaction Codes (System)	89	180 - Standard Note Doc Types (System)	89
146 - Acct Log Transaction Codes (System)	89	181 - Asset Inspection Type Asset Inspection Data Module	176
148 - Bin Transaction Codes (System)	89	182 - Asset Inspection Reason Asset Inspection Data Module	176
149 - Requisition Types (System)	89	183 - Weather Condition Asset Inspection Data Module	176
150 - Confirmation Types Purchase Order Module	386	184 - Approval Doc Types (System)	89
151- Purchasing Item Types (System)	89	185 - Apprvl Rtnng Doc Types (System)	89
154 - Expediting Item Status Purchase Order Module	386	186 - Manufacturer Codes	50
155 - Purchase Order Types (System)	89	187 - Inventory Adjustment Reason Codes (DBA) Storeroom Module	90, 146
156 - Invoice AP Procsng Chk Codes (DBA)	90	188 - Manual Hold Adjstmt Reasons (DBA)	90
157 - Invoice Prorate Options Invoicing Module	409	189 - Work Action Codes Work Order Task Module	269
158 - Invoice Pay To Vendor Ind (System)	89	190 - Job Codes Fleet Work Order Task Module	290
159 - Federal Tax Codes Invoicing Module	402, 409	Work Order Task Module	268
Master Catalog Module	154	191 - Work Order Job Codes (Obsolete)	91
Purchase Order Module	386	192 - Supplier (AMMO)	91
Requisition Module	375	193 - PM Forecast Adjustment Codes (System)	89
Work Design Module	244	194 - Action (AMMO)	91
160 - State Tax Codes Invoicing Module	409	195 - Problem Trend (AMMO)	91
Master Catalog Module	154	196 - Category Trend (AMMO)	92
Purchase Order Module	386	197 - Group Trend (AMMO)	92
Requisition Module	375	198 - PM Categories PM Master Module	305
Work Design Module	244	199 - Disposition Trend (AMMO)	92
161 - Duty Codes Invoicing Module	409	201 - Quantity Classes (AMMO)	92
Master Catalog Module	154	202 - Storage Codes Master Catalog Module	155
Purchase Order Module	386	203 - Special Requirements Master Catalog Module	155
Requisition Module	375	204 - Shelf Life Units (System)	89
Work Design Module	244	205 - Route Description Codes (Obsolete)	91
162 - Dispose of Asset Transaction Types Change Request Module	196	206 - PM Route Types (Obsolete)	91
163 - Change Asset Configuration Transaction Types Change Request Module	196		
165 - Change Request Types Change Request Module	196		
166 - Change Request Classes Change Request Module	196		
167 - Impact Types Change Request Module	196		

208 - Employee Job Title Employee Module	204	254 - Mid Level Acct Sgmnt 4 (DBA)	90
		Account Module	137
		Account Structure Module	127
209 - Relationship Types Master Catalog Module	155	255 - Low Level Acct Sgmnt 5 (DBA)	90
		Account Module	137
		Account Structure Module	127
212 - Item Class Codes Master Catalog Module	154	256 - Flex Acct Number 6 (DBA)	90
Master Catalog Module1	459	Account Module	137
		Account Structure Module	127
214 - Inspection Types (AMMO)	92	257 - Account Number (DBA)	90
215 - Inspection Category (AMMO)	92	Account Module	137
220 - Drawing Types (Obsolete)	91	Account Structure Module	127
221 - Component Types Component ID Module	181	258 - Account Number (DBA)	90
		Account Module	137
222 - Component Category Work Order Task Module	269	Account Structure Module	127
		259 - Account Number (DBA)	90
224 - Compatible Unit Difficulty Compatible Unit Module	189	Account Module	137
		Account Structure Module	127
225 - Compatible Unit Business Unit Compatible Structure Module	186	260 - Account Number (DBA)	90
Compatible Unit Module	189	Account Module	137
		Account Structure Module	127
226 - Compatible Unit Class Compatible Structure Module	186	276 - Document Media Types Document Control Module	215
Compatible Unit Module	189		
227 - Compatible Unit Equipment Group Compatible Structure Module	186	281 - Report Codes Fleet Work Order Task Module	290
Compatible Unit Module	189	Work Order Task Module	268
		282 - Report Codes Fleet Work Order Task Module	290
229 - Non-Eqpmnt Asset Records (System)	89	Work Order Task Module	268
230 - Asset Record Types Asset Module	162	283 - Report Codes Fleet Work Order Task Module	290
Component ID Module	181	Work Order Task Module	268
		284 - Report Codes Fleet Work Order Task Module	290
231 - Location Asset Module	163	Work Order Task Module	268
Process Module	228	285 - Report Codes Fleet Work Order Task Module	290
		Work Order Task Module	268
240 - Service Request Types Service Request Module	468	286 - Account Treatment Type (System)	89
		287 - Tracking Method (System)	89
241 - Problem Codes Service Request Module	468	288 - Assessment Status (System)	89
		289 - Service Request Status (System)	89
242 - Deposit and Payment Types Service Request Module	468	290 - Storeroom Auto-Reorder Sources (System)	89
		291 - Work Status (System)	89
243 - Process Level Invoice Batch Module	410	292 - Condition Rating Basis (System)	89
		293 - Delivery Lead Time Units (System)	89
244 - Ground Condition Asset Inspection Data Module	176	294 - Folders (System)	89
		295 - Item Type (System)	89
245 - Inspection Severity Asset Inspection Data Module	176	296 - Req Status Type (System)	89
		297 - Rfq Status Type (System)	89
246 - Disconnect Location Service Request Module	468	298 - Downtime Indicator (System)	89
		299 - Weekly Schedule Indicator (System)	89
251 - Personal ID Acct Sgmnt 1 (DBA)	90	300 - Daily Schedule Indicator (System)	89
Account Module	137	301 - Held For Parts Indicator (System)	89
Account Structure Module	127		
252 - Area/Dept? Acct Sgmnt 2 (DBA)	90		
Account Module	137		
Account Structure Module	127		
253 - High Level Acct Sgmnt 3 (DBA)	90		
Account Module	137		
Account Structure Module	127		

302 - Change Request Indicator (System)	89	Keys and Locks Module	230
303 - Po Status Type (System)	89	550 - Direct Charge Category Codes	
304 - Asset/Fleet (System)	89	Direct Charges Module	339
310 - Supervisor Title		560 - Workshop Codes (DBA)	90
Crew Module	276	Configuration Guide Module	93
Employee Module	204	561 - Subsystem Codes (DBA)	90
Employee Timekeeping Module	346	Configuration Guide Module	93
Project Module	321	562 - Module Codes (DBA)	90
320 - Facility Types (AMMO)	92	Configuration Guide Module	93
321 - Bin Types (AMMO)	92	563 - Function Codes (DBA)	90
322 - Bin Level (AMMO)	92	Configuration Guide Module	93
323 - Bin Storage Types (AMMO)	92	564 - Decision Status Codes (DBA)	90
324 - Bin Orientation (AMMO)	92	Configuration Guide Module	93
325 - Bin Document Types (AMMO)	92	565 - Priority Codes (DBA)	91
340 - PM Master Units (Obsolete)	91	Configuration Guide Module	93
341 - FMEA Template Detection Code (DBA)	90	570 - Hour	
341 - FMEA Template Occurrence Code (DBA)	90	Operational Schedule Module	293
341 - FMEA Template Severity Code		571 - Minute	
FMEA Template Module	315	Operational Schedule Module	293
341 - FMEA Template Severity Code (DBA)	90	600 - Asset Class (Not Used)	91
360 - Quality Classes		601 - Asset Class Type	
Master Catalog Module	154	Asset Class Module	172
361 - EDI Transaction Types (AMMO)	92	660 - Vehicle Reason for Repair	
409 - Document Classifications Codes		Fleet Work Order Task Module	290
Document Control Module	215	Work Order Task Module	268
410 - Document File Types		661 - Vehicle Action Taken	
Document Control Module	215	Fleet Work Order Task Module	290
450 - Standards Categories (System)	89	Work Order Task Module	268
451 - Unit Code Asset Segment 1 (DBA)	90	662 - Vehicle System	
452 - System Code Asset Segment 2 (DBA)	90	Fleet Work Order Module	290
453 - Designator Code Asset Sgmt 3 (DBA)	90	Work Order Task Module	268
454 - Asset Segment 4 (DBA)	90	700 - Job Reference Codes	
455 - Type Asset Segment 5 (DBA)	90	Service Contract Invoice Module	418
456 - Asset Segment 6 (DBA)	90	Service Contract Timesheets Module	421
457 - Asset Segment 7 (DBA)	90	710 - Week Days	
458 - Asset Segment 8 (DBA)	90	Operational Schedule Module	293
459 - Asset Segment 9 (DBA)	90	730 - Contribution in Aid to Construction	
460 - Asset Segment 10 (DBA)	90	Work Design Module	244
470 - Job Hazard Type		731 - Work Design Cost Type	
Job Hazard Module	225	Work Design Module	244
471 - Job Hazard Category		732 - Location Structure Type	
Job Hazard Module	225	Work Design Module	244
472 - Protective Equipment		800 - Graph Colors (System)	89
Job Hazard Module	225	1050 - Precedence Relationship Code	
510 - Vehicle Organization		Work Order Task Module	268
Fleet Asset Module	286	1110 - Schedule Plan Summary Label	89
511 - Vehicle Sub-Organization		1150 - Vehicle Assembly	
Fleet Asset Module	286	Fleet Work Order Task Module	290
512 - Monitoring Group		1151 - Vehicle Components	
Fleet Asset Module	286	Fleet Work Order Task Module	290
515- Keys and Locks Set Types		1190 - Daily Schedule Types	
		Daily Schedule Module	333
		1191- Schedule Interruption Codes	
		Daily Schedule Module	333

1192 - RIVA Asset Type		Bill of Materials (BOMDATA)	194
Asset Module	163	Blanket Contract (BLNKTCO)	397
1193 - Tag Point Category		Change Request (CHNGREQ)	198
Tag Point Module	301	Checkout Request (CHKREQST)	428
1195 - CCB Expense		Chemical Label (MSDSCH)	217
Account Module	137	Compatible Structure (COMPSTRU)	186
Service Request Module	468	Component (COMPID)	185
1196 - CCB Install Remove Flag		Crew (CREWMOD)	276
Account Module	137	Customer (CUSTOMER)	465
Service Request Module	468	Department (DEPT)	132
1197 - Compatible Unit Type		Direct Charges (ODC)	341
Compatible Unit Module	189	Document Control (DOCUMENT)	215
2105 - Days of the Week	89	Employee (EMPLOYEE)	204
2500 - Daily Schedule Types		Fleet Asset (FLTASSET)	286
Workweek Schedule Module	337	Fleet Benchmark WO (BENCHFLT)	291
2501 - Interruption Code		Fleet Operational Schedule (OPERSCHED)	293
Daily Workweek Module	337	Fleet PM Control (FLEETPMC)	317
Checklist Title (user-defined)		Function (FUNCTION)	226
Permit Template Module	294	Job Hazard (JOBHZRD)	225
Duration (user-defined)		Leave Request (LEAVEREQ)	344
Permit Template Module	294	Maintenance Manager (MAINTMGR)	230
Comp Time	353	Master Catalog (CATALOG)	155
Company Module	470	MS Project	328
Compatible Structure Module	186	MSDS (MSDS)	217
Compatible Unit Defaults Business Rule		Operational Tolerance (OPERTOL)	178
Compatible Units Module	190	Permit (PERMIT)	299
Compatible Unit Function Business Rule		Permit Template (PERMTMPL)	295
Compatible Units Module	191	PM Event (PMEVENT)	313
Work Design Module	242	PM Master (PMMASTER)	309
Compatible Unit Module	188	PM Route (PMROUTE)	320
Component ID Module	180	Procedure (PROCEDUR)	223
Component ID Rule Business Rule		Process (PROCESS)	229
Component ID Module	181	Project/Subproject (PROJECT)	321
Component Processing Business Rule		Property Management (PROPERTY)	463
Component ID Module	182	Regulatory Account (REGACCT)	142
Component Upload	185	Request For Quotes (RFQ)	400
Condition Assessment View		Responsibility (RESPONBL)	114
Asset Class Module	172	Service Contract (SERVCONTR)	417
Configuration Guide Module	93	Service Request (SERVREQ)	468
Consumables Module	464	Service Timesheet (CTIMESHT)	421
Copy Record	102	Shipping Memo (SHIPMEMO)	462
Account (ACCTDATA)	137	Standard Notes (STDNOTES)	220
Account Distribution (ACCTTMPL)	139	Storeroom (STORERM)	147
Activity Tracking (ACTTRACK)	279	Storeroom Setup (STORESET)	151
Approval Limit (APPROVAL)	74	Tag List (TAGLIST)	304
Approval Routing (ROUTELIST)	76	Tag Point (TAGPOINT)	302
Area (AREA)	132	Timesheet (TIMESHT)	357
Asset (ASSET)	163	User Profile (USERPROF)	121
Asset Class (ASSETCLS)	172		
Benchmark Work Order (BENCHWO)	274		

Vendor (VENDOR)	365	Timekeeping DTA REgular Type	81
Warranty (WARRANTY)	413	Custom Menu View	
Work Design (WODESIGN)	245	Modules Administration - Forms Modules	103
Work Request (WORKREQ)	239	Customer Module	465
Copy Record View		Customized	
Modules Administration - Forms Module	102	field labels	59
Copy/Paste Object IDs Business Rule (General)	37	D	
Cost Adjustment Module	414	Daily Schedule Module	331
Cost Adjustments Business Rule		Database Administration	53
Cost Adjustment Module	414	DBA Code Tables	90
Craft Rates Business Rule		dbp_end_period_depreciation	67
Crew Module	276	Debugging Batch Jobs	72
Employee Module	201	Default Backlog Groups Business Rule	
Employee Timekeeping Module	346	Daily Schedule Module	332
Crafts View		PM Master Module	306
Master Catalog Module	156	Work Order Task Module	259
Credit Card Purchases Business Rule		Work Request Module	234
Purchase Order Module	381	Workweek Schedule Module	336
Requisition Module	372	Default Directories Business Rule	
Work Order Task Module	258	Component ID Module	183
Crew Activity Log Module	278	Operational Data Module	179
Crew Daily Hours View		Receiving Module	444
Crew Module	277	Request for Quotes Module	398
Crew Employee Assignment View		Default Directories Business Rule (General)	38
Crew Module	277	Default File Locations Business Rule (General)	39
Crew Module	275	Default Work Request Req Date Business Rule	
Criticality Override Business Rule		Work Request Module	235
Asset Module	158	Defining Tables	123
Work Order Task Module	258	Department Module	132
Work Request Module	234	Depreciation Parameters View	
Currency Codes	60	Asset Class Module	174
Currency Exchange Rates Module	93	Direct Charge Types Business Rule	
Custom Business Rules		Direct Charges Module	340
Account Rules	80	Direct Charges Module	339
Analysis Views Access List	80	Do Approvals Query	
AP Batch Interface	80	General System Settings	40
EDI Transaction Codes	80	Do Attachments Query	
GIS Asset Interface	80, 81	General System Settings	40
GIS Setup	81	Do Notes Query	
GIS View Attributes	81	General System Settings	40
Interfaces	81	Document Control Module	215
Oracle CAI Financials Admin	81	Document Storage Types Business Rule	
Oracle Financials	81	Attachment Modules	207
Oracle Purchasing	81	Downtime Type By Work Type Rule	
Report Labels	81	Fleet Asset Module	283
RFGen Barcoding Setup	81	Drilldown Configuration Business Rule	
SAIF Charge Numbers Interface	81	Asset Navigator	41
Timekeeping DTA Pay Code	81		

Duplicate View		Activate PINs	121
Modules Administration - Forms Modules	104	Activate WO Material	254, 318
E		Add Customer Contributed	254, 318
EDI Transaction Codes Business Rule (Custom)	80	Add Dependent Materials	269
Email Configuration Business Rule (General)	43	Add Items from Work Order	429
Employee Module	200	Add Tag Points	299
Employee Timekeeping Module	346	Add Vendor After RFQ Issued	400
End of Period Processing Business Rule		Add/Delete Job Hazard	224
Accounting Periods Module	129	Adjust Store for Recount	460
Pay Periods Module	129	Allow WO Project Update	254, 327
Enforce Receiver Business Rule		Approve All Timesheets	357
Receiving Module	445	Assign Contractor to CUs	269
Enhanced Security	53	Associate Tag List	304
Enter Data View		Associated Service Request	469
Modules Administration - Forms Module	101	Award RFQ	400
Enterprise Asset Module	470	Bar Code Print Labels	448, 453
Enterprise Catalog Module	470	Cancel PM Master Backlog	310
Event Queue	51	Change PO Auto Pay Indicator	386
Expense Codes Business Rule		Change Request Actions for AVL	198
Account Module	136	Change Request Asset	198
Service Request Module	467	Change Request Catalog/Storem	198
F		Checkout All Planned Items	434
Failed Logon Attempts	54	Copy PO from PO	386
Federal Tax Rebate Business Rule		Copy Service Timesheet	422
Invoicing Module	402	Copy to New Compatible Unit	191
FGA Responsibility Module	95	Copy to New Service Contract	422
Field Labels	59	Cost and Closeout	269, 341, 357
Field Localization View		Create Activity Log From Asset	163, 169, 287
Modules Administration - Forms Module	101	Create Blanket Contract Revs	397
Fine Grain Access Module	94	Create Blnket Contract Rev Hist	397
Fleet Asset Module	280	Create Checkout Request frm WO	269, 289
Fleet Benchmark Work Order Module	291	Create Emergency WO Asset	163, 169, 254
Fleet Constants Business Rule		Create Emergency WO FleetAsset	254, 286
Fleet Asset Module	283	Create Emergency Work Order	254
Fleet Mileage Reasonability Business Rule		Create FMEA Failure Item	315
Fleet Asset Module	284	Create FMEA PM Control	315
Fleet Reservations/Motorpool Module	292	Create New Procedure Revision	224
Fleet Work Order Module	288	Create Permit From WO	254
Fleet Work Order Task Module	288, 290	Create Req from Blanket	375
FMEA Template Module	314	Create Shipping Memo	375
FMEA Template RPN Defaults Business Rule		Create Specification	163, 169
FMEA Template Module	314	Create Tag List	303
Function Module	226	Create Templates from Req	375
Functions	223, 225, 310, 334, 337	Create Warranty Claim	411, 412
Accept Quality Items	453	Create WO from Benchmark	254, 274
Activate Chkout Req from Sched	334, 429	Create WO from Service Request	469
		Create WO From Work Design	244
		Create Work Order	195, 254, 288, 315

Create Work Order Asset	163, 169, 254	Revise Procedure	225
Create Work Order Component	185, 254	Route Timesheet for Approval	357
Create Work Order FleetAsset	254, 286	Route to Designer	244
Create Work Order Process	228, 254	Search Duplicate Permits	255
Create Work Request	239	Serv Invoice Account Override	420
Create Work Request Asset	163, 169, 239	Service Contract to Active	422
Create Work Request Component	185, 239	Service Invoice Export Wizard	420
Create Work Request FleetAsset	239, 286	Set Vendor Auto Pay Indicator	366
Create Work Request Process	228, 239	Show CU Location	191, 255, 270
Credit PM	310	Show CU on WO	191, 255, 270
Disable Custom SQL	51	Show Cycle PM Group Now Action	310
Display Accrual Tax Total	408	Show Cycle This PM Now Action	310
Display Trusted Sites Link	109	Storeroom ABC	137, 147
Document to Active	215	Storeroom Adjustment	137, 147
Duplicate Blanket to PO	397	Storeroom Reorder	137, 147
Employee SSN	204	Subproject Approved to Created	327
Employee Wage Rate	204	Subproject Finish to Approved	327
Entity Relationship Viewer	52	Tag All	299
ESRI2 Viewer	52	Timesheet Wizard	357, 358
Export RFQ	400	Transfer Canceled PO Items	386
GIS Viewer	52	Update Active CU/CS	187, 192
Graph Viewer	52	Update Benchmark WO	255
Import RFQ	400	Update BOM	195
Invoice - Override Discrepant	409	Update Estimate Hours	310
Invoice - Resolve Discrepant	409	Update Estimate Qty	310
Invoice Account Override	408	Update Pricing on WD	244
Invoice Pay to Vendors	409	Update Process on Work Order	255
Issue RFQ	400	Update Reg Acct Dist	270
Issue Uncompiled Objects Msg	52	Update WO from Benchmark	255
Log Fleet Downtime	289	Fleet	289
Merge Task WOWeek to Day Schd	334, 337	User Profile Administrator	121
Modify Job Hazard	224	Value Assets in Prior Year	270
MSR Force PO Complete	453	Verify All	299
News Administration	52	View External Actual Costs	137
Not_Vendor_Caused	453	View GIS	163
Not_Vendor_Caused	454	WO Active to Planning	255
Permit to Active	299	WO Closed to Finished	254, 318
Project Closed to Finished	327	WO Finished to Active	254, 318
Project Finished to Closed	327	WO Finished to Closed	254, 318
Project Management	327	WO Task to Active	270
Receive All Items As Ordered	448, 454	WO to Active	254, 318
Receive More Than Ordered	448, 454	Work Type Update	255
Reconcile CUs	255		
Release All	299		
Reorder Wizard	52, 137, 147, 442		
Repair Removed Part	254, 269, 288, 318, 429, 456		
Replace CU Material Item	191		
Resend Approval Request	375, 386, 391		

G

General Configuration

Batch Job Control Business Rule	63
Copy/Paste Object IDs Business Rule	37
Default Directories Business Rule	38

Default File Locations Business Rule	39	Accrual	83
Email Configuration Business Rule	43	Asset	83
Optional Message Presentation Business Rule ...	44, 432	Catalog	83
Primary Menu Business Rule	46	Customer	83
Restrict List of Values Business Rule	47	Customer Address Interface	83
Spell Check Business Rule	48	Customer SA Interface	83
UDFs - Auto Copy Across Modules Business Rule	49	Default Accts for Interfaces	83
Unit of Measurement Business Rule	50	Employee	83
GIS Asset Interface Rule (Custom)	80, 81	GL Transaction	83
GIS Setup Rule (Custom)	81	Interface Parameters	84
GIS View Attributes Rule (Custom)	81	Interfaces	83
H		Manufacturer Vendor	83
Help		Service Request	83
customizing	97	Storeroom	83
Help Form Module	97	Vendor	83
Holidays Business Rule		Internal Tracking Options Business Rule (AMMO)	84
Employee Timekeeping Module	346	Invoice Batch Module	410
Home Page Component Alias		Invoice Prorate Defaults Business Rule	
Home Page	41	Invoicing Module	405
I		Invoice Setup Criteria Business Rule	
Inspection Criteria View		Invoicing Module	403
Asset Class Module	174	Storeroom Module	144
Inspection Report Generation Business Rule (AMMO)	84	Invoice Tolerances Business Rule	
Installation Parameters	98	Invoicing Module	406
audit log	52, 53	Invoicing Module	402
batch job debugging	72	J	
chart thumbnails	110	Job Hazard Module	225
chart valuation	109	Job Manager Module	62
module	98	K	
password reset	52	Keys and Locks Module	230
phone numbers	52	L	
spell check	52	Labels	
system-wide	52, 109	field labels	59
workflow message dialog	53	Labor Burden Multipliers Business Rule	
Integration Business Rules	82	Employee Timekeeping Module	347
Product Integration	82	Labor Costing Markup Business Rule	
Product Integration CCB	82	Employee Timekeeping Module	348
Product Integration CCB Contacts	82	Labor Costing Wage Rates Business Rule	
Product Integration CCB FA Types	82	Employee Timekeeping Module	348
Product Integration CCB Status	82	Leave Request Module	342
Product Integration Field Work	82	Locale	60
Standard Service Request Interface	82	Localization	58, 59, 101
Web Services Gateway	82	code tables	61
Interfaces Business Rule (Custom)	81	currency codes	60
Interfaces Business Rules		field labels	59
Account Interface	83	locale	60

phone formats	60
Log Files	54
Logging In	
failed attempts	54
Login	
single sign on	56
Logoff	57
M	
Maintenance Manager Module	230
Master Catalog Module	152
Material Disposition Module	455
MDI Window Title Business Rule	
Home Page	42
Metrics	106
Customer Follow-Up Calls Pending	469
disabling thumbnails	110
External Time to Receive Parts	388
Internal Time to Issue PO	387
Late PMs	312
Late PMs for Safety Equipment	312
Percent Emergency Work	256
Percent of Planned Downtime	164, 170
Percent PM Investment	256, 311
Percent Preventive Work	256, 311
Total Lead Time	376, 388
Microsoft Project	328
Microsoft Project Interface	
Project Module	328
Modules	
Warranty Claim Module	411
Warranty Module	412
Modules Administration	
forms	101
sia	104
Modules Requiring an Approval Title	
Change Order Module	74
Change Request Module - Asset	74
Change Request Module - Catalog	74
Change Request Module - Generic	74
Change Request Module - Storeroom	74
Change Request Module - Vendor	74
Cost Adjustment Module	74
Crew Module - WO Task Assignment	74
Direct Charges Log	74
Direct Charges Module	74
Employee Timekeeping Module	74
Invoicing Module	74

Leave Request Module	74
Permits Module	74
Procedures Module	74
Project Module	74
Purchase Order Module	74
Request for Quotes Module	74
Requisition Module	74
Service Contract Timesheet Module	74
Service Request Module	74
Work Order Module	74
Work Request Module	74
MS Project	
configuration	328
MSDS Chemical Label Module	217
MSDS Module	217
Multiple Active Contracts Business Rule	
Blanket Contract Module	393
Multi-Step Receiving Module	449
O	
Obsolete Business Rules	84
Obsolete Code Tables	91
Operational Asset Data Module	179
Operational Data Module	178
Operational Schedule Module	293
Operational Tolerance Module	178
Optional Message Presentation Business Rule	
Stock Checkout Module	432
Optional Message Presentation Business Rule (General) ..	44
Oracle CAI Financials Admin Business Rule (Custom)	81
Oracle Financials Business Rule (Custom)	81
Oracle Purchasing Business Rule (Custom)	81
Organization Module	471
OUBI Setup Business Rule	81
Overtime Standings Business Rule	
Employee Timekeeping Module	349
P	
Page Redirection	57
Password	
enhanced security	53
install parameter for reset	52
security business rule	119
Password Security Business Rule	
User Profile Module	119
Pay Periods Module	129
Payment Terms Business Rule	
Invoicing Module	407

Vendor Module	361	PO Aging Rules Business Rule	
Payroll Voucher Module	345	Purchase Order Module	381
Payroll Voucher Types Business Rule		PO Report Constants Business Rule	
Payroll Voucher Module	345	Purchase Order Module	382
Period Costs View		Work Design Module	242
Account Module	138	PO Report Status Codes Business Rule	
Permit Processing Business Rule		Purchase Order Module	383
Permits Module	298	Primary Menu Business Rule (General)	46
Permit Template Module	294	Printer Alias Business Rule	
Permit Template Requirements View		Attachment Modules	207
Asset Module	166	User Profile Module	120
Permit Type Business Rule		Printing	
Permits Module	297	attachments	205
Tag Point Module	302	Procedure Attachment Update Business Rule	
Permits Module	296	Procedure Module	222
Phone Formats	60	Procedure Module	221
Phone Numbers	52	Procedures Authority Business Rule	
Physical Inventory Module	458	Procedure Module	223
Physical Inventory Rules Business Rule		Process Module	227
Physical Inventory Module	458	Procurement Level Business Rule	
Physical Inventory Tolerances Business Rule		Master Catalog Module	152
Physical Inventory Module	459	Project Budget Options Business Rule	
PIN Processing Administration Business Rule		Project Module	323
User Profile Module	45	Project Management Business Rule	
Planner Business Rule		Project/Subproject Module	325
Asset Module	159, 284	Project Work Order Account Business Rule	
Process Module	228	Project/ Subproject Module	326
Work Order Module	250	Project/Subproject Module	321
Work Order Task Module	259	Property Management Module	463
Work Request Module	236	Proxies	55
Planner Rule		Purchase Order Module	377
Fleet Asset Module	285	Purchasing Log Module	416
Plant Module	471	Purchasing Options Business Rule	
PM ControlTypes Business Rule		Blanket Contract Module	395
Asset PM Control Module	317	Change Order Module	391
PM Event Module	313	Invoicing Module	408
PM Master Module	305	Purchase Order Module	384
PM Master Parameters Business Rule		Requisition Module	373
PM Master Module	306	Q	
PM Route Module	319	Quote Options Business Rule (AMMO)	84
PM Route Options Business Rule		R	
PM Route Module	319	Receiving (Multi-Step)	449
Work Order Task Module	260	Receiving Configuration Business Rule	
PM Schedule Basis Rule		Multi-Step Receiving Module	451
PM Master Module	308	Receiving Module	445
PM Seasonal Adjustments Business Rule		Stock Transfer Module	436
PM Master Module	309		

Receiving Module	443	Inspection/Discrepancy Physical Inventory	460
Redirect Logoff	57	Inventory Picklist	148, 257, 429
Regulatory Account Options Business Rule		Inventory Picklist - Bar Code	149, 257, 429, 437
Regulatory Account Module	141	Invoice Variance	409
Regulatory Account Overhead Class Business Rule		Issue Ticket	434
Regulatory Account Module	141	Job Manager Log	71
Regulatory Account Usage Codes Business Rule		Labor Distribution by Account	358
Regulatory Account Module	140	Labor Distribution by Employee	358
Regulatory Accounting Module	140	Labor Expenditure Summary by Account	358
Reorder Review Module	439	Listing of Completed NCMs	454
Repairable Processing Business Rule		Lockout/Tagout	300
Material Disposition Module	455	Mechanic Accountability	287
Report Administration Module	111	New Stock Items	149
Report Labels Business Rule (Custom)	81	New Storeroom Items	149
Reports	58, 106	Open Purchase Order Detail	388
About to Reorder	442	Open Purchase Order Summary	388
Accruals By Account	388	Overstock	149
add to modules	101	Overtime Standing by Crew	276, 358
Asset Inspection Worksheet	176	Overtime Standing by Zone	358
Asset Listing By Type and Class	164	Payroll	358
Bill of Material	195	Physical Inventory Listing	460
Blanket Contract	397	Physical Inventory Variance	460
Business Rule	80	PM By Asset	164, 310
Catalog (without Quantities)	148	PM Route	320
Catalog Non-Usage	148	Preventive Maintenance	310
Change Request	199	Procedures	224
Code Table	88	Process	229
Code Table Definition	88	Process with Asset Detail	164
Compatible Units Audit Report	192	Property Inventory - Discrepancies	463
Component ID	185	Property Inventory - Items Not Found	460, 463
Confined Space	299	Property Inventory - Items to be Inventoried	463
Confined Space (Blank)	299	Purchase Order	389
Contract PO Activity	388	Purchase Order - Department Copy	388
Daily Schedule	270, 334	Purchase Order - Finance Copy	389
Daily Schedule Assignments	334	Purchase Order - Not Yet Received	389
Deficient Vendors	366	Purchase Order - Records with Returns	389
Delivery Receiving	388, 448, 454	Purchase Order - Vendor Copy	366, 389
Delivery Ticket	388	Purchase Order Accruals (Unpaid POs)	388
Employee	204	Purchase Order Accruals (Unpaid Receipts)	388, 409
Employee Pay Period Time	344	Purchase Order Expensing Account Detail	137, 388
Employee Timesheet	358	Purchase Order Inventory Item Cost	149, 388
Equipment History Summary	287	Purchase Order Listing by PO Number	388
Equipment List by Shop	287	Purchase Order Listing by Vendor Code	366, 388
Historic Cost Performance by Asset	164, 257	Purchase Order Over Received	388
Historical Cost Performance	287	Purchase Order Report w/Notes & Atchmnts	389
Holiday Overtime Standing	204, 257	Purchase Order Vendor	366, 389
Hot Work Permit	299	Ready for Payment	389
Hot Work Permit (Blank)	299	Receipt Delivery Worksheet	448, 454

Receiving	389, 448, 454
Receiving Worksheet	389, 448, 454
Request for Quotes	401
Requisition	376
Requisitions (by Vendor)	376
Reservation Dispatch	292
Safety Work Permit	300
Schedule Plan	338
Service Contract Accrued Cost	417
Service Contract Details	417
Service Contract Summary	417
Service Requests	469
Shipping Memo	462
Specification	218
Stock Transfer	149, 437
Stock Transfer - Barcode	437
Storeroom Activity	149
Storeroom Value by Class	149
Storeroom Value Report by Stock Code	149
Storeroom Value Report by Vendor	367
Storeroom with Quantities	149
Superior Vendor Performance Data	367
Tax Report for Inventoried Stocked Items	149
Tax Report for Non-Stocked Items	149
Understock Report	149
Vendor Characteristics	367
Vendor Classification Activity	367
Vendor Label	367
Vendor Listing	367
Vendor Performance by Buyer	367
Vendor Performance Data	367
Vendors with 3 or More Deficiencies	367
Wage Rate History	204
Work Design	244
Work Design Comparison	244
Work Design Estimate	244
Work Order (Condensed)	257
Work Order Aging	257
Work Order Backlog	270
Work Order Backlog Detail	270
Work Order Forecast	257
Work Order Package	257
Work Order Task Aging	270
Work Order Tasks Delayed by Materials	270
Work Request Summary	240, 244
Workweek Schedule	270

Request for Quotes Module	398
Required Fields View	
Modules Administration - Forms Module	101
Requisition Module	368
Requisition to PO Rule Business Rule	
Requisition Module	372
Reservations/Motorpool Module	292
Responsibility Module	113
Restrict List of Values Business Rule (General)	47
RFGen Barcoding Setup Business Rule (Custom)	81
Routing List Module	75
Runtime Entry Module	330

S

S_RPT071 Crew Craft Columns Business Rule	
Work Order Module	251
SAIF Charge Numbers Infrce Bus Rule (Custom)	81
SAPI	58
SAPI Triggers	103
Schedule Plan Module	338
Scheduled Holidays Business Rule	
Employee Module	201
Employee Timekeeping Module	349
Scheduling Options Business Rule	
Daily Schedule Module	333
Secondary Fields View	
Modules Administration - SIA Modules	105
Secondary Required Fields View	
Modules Administration - Forms Module	101
Security	55
certificate	56
Selection Order By View	
Modules Administration - Forms Modules	103
Sequence Numbers	
Account Distribution (SA_ACCOUNT_DISTRIBUTION) ..	139
Activity Tracking (SA_ACTIVITY_TRACKING)	279
Asset (ASSET)	157
Asset Activity Log (SA_ASSET_ACTIVITY_LOG)	169
Asset Inspection Data (SA_ASSET_INSPECTION) ..	176
Benchmark Work Order (BENCHMARK)	273
Bill of Materials (SA_BOM_DATA)	194
Blanket Contract (SA_BLANKET_CONTRACT)	392
Change Request (SA_CHANGE_REQUEST)	196
Compatible Structure (SA_COMPATIBLE_STRUCTURE)	186
Compatible Unit (SA_COMPATIBLE_UNIT)	188
Component ID (SA_COMPONENT_ID)	180
Cost Adjustment (SA_ADJUSTMENT)	414

Customer (SA_CUSTOMER)	465	INSPECTION (SA_INSPECTION)	85
Direct Charges (SA_DIRECT_CHARGES)	339	INSPECTION TEMPLATE (SA_INSPECT_TEMPLATE) .	85
Document Control (SA_DOCUMENT)	215	INTERNAL TRACKING (SA_INTERNAL_TRACKING)	85
Employee (SA_EMPLOYEE)	200	INVENTORY LOG (SA_INVENTORY_LOG)	85
Fine Grain Access (SA_FINE_GRAIN_ACCESS)	94	RETURN REQUEST (SA_RETURN_REQUEST)	85
Fleet Asset (FLEET)	152, 280	STOREROOM REORDER HISTORY	
Fleet Benchmark Work Order (BENCHMARK)	291	(SA_STOREROOM_REORDER_HISTORY)	85
Fleet PM Control (SA_PM_FLEET_CONTROL)	316	Sequence Numbers Module	116
Fleet Work Order (SA_WORK_ORDER)	288	Serv Invoice Account Override Business Rule	
Function (FUNCTION)	226	Service Contract Invoice Module	418
Invoice Batch (SA_INVOICE_BATCH)	410	Serv Invoice Prorate Defaults Business Rule	
Job Hazard (SA_JOB_HAZARD)	225	Service Contract Invoice Module	419
Master Catalog (SA_CATALOG)	152	Serv Invoice Tolerances Business Rule	
Multi-Step Receiving (SA_DELIVERY)	449	Service Contract Invoice Module	420
Operational Schedule (SA_OPERATIONAL_SCHEDULE)	293	Service Contract Invoice Module	418
Operational Tolerances		Service Contract Module	417
(SA_OPERATIONAL_TOLERANCES)	178	Service Contract Timesheets Module	421
Permit Template (SA_PERMIT_TEMPLATE)	294	Service Request Module	467
Permits (SA_PERMIT)	296	Service Timesheet Charge Types Business Rule	
PM Master (SA_PM_MASTER)	305	Service Contract Timesheets Module	421
Procedure (SA_PROCEDURES)	221	Shelf Life Rule Business Rule	
Project (SA_PROJECT)	321	Master Catalog Module	153
Property Management (SA_PROPERTY)	463	Shift Differential Rates Business Rule	
Purchase Order (SA_PURCHASE_ORDER)	377	Employee Timekeeping Module	350
Request for Quotes (SA_QUOTE)	398	Shipping Memo Module	461
Requisition (SA_REQUISITION)	368	Shipping Memo Options Business Rule	
Reservations/Motorpool (SA_FLEET_RESERVATIONS) .	292	Shipping Memo Module	461
Service Contracts (SA_SERVICE_CONTRACT)	417	Single Sign On	56
Service Request (SA_SERVICE_REQUEST)	467	Special LOV's View	
Shipping Memo (SA_SHIPPING_MEMO)	461	Modules Administration - Forms Modules	103
Specification Template (SA_SPECIFICATION_DATA)	218	Specification Configuration	219
Standard Notes (SA_STANDARD_NOTES)	220	Specification Module	218
Tag List (SA_TAG_LIST)	304	Specification Template Module	218
Tag Point (SA_TAG_POINT)	301	Lists of Values for	219
Vendor (SA_VENDOR)	360	Specification Upload Defaults Business Rule	
Warranty (SA_MFR_WARRANTY)	412	Component ID Module	184
Warranty Claim (SA_MFR_WARRANTY_CLAIM)	411	Receiving Module	446
Work Design (SA_WORK_DESIGN)	241	Spell Check Business Rule (General)	48
Work Order (SA_WORK_ORDER)	246, 314	Standard Notes Module	220
Work Order Task Failure		Status Required Fields View	
(SA_WORK_ORDER_TASK_FAILURE)	246, 314	Modules Administration - Forms Module	101
Work Request (SA_WORK_REQUEST)	231	Stock Checkout Module	430
Sequence Numbers (obsolete)		Stock Transfer Module	435
ASSET INSPECTION		Storeroom Demand Allocation Business Rule	
(SA_ASSET_INSPECTION_DETAIL)	84	Checkout Request Module	426
BIN (SA_BIN)	84	Storeroom Module	146
BIN RELOCATION (SA_BIN_RELOCATION)	85		
DISCREPANCY (SA_DISCREPANCY)	85		

Storeroom Module	143
chart valuation	109
Storeroom Setup Module	150
Storeroom Stocking Module	438
Stores Transaction Groups Business Rule (Obsolete)	84
Subproject View	
Project Module	328
System Code Tables	88
T	
Tag List Module	304
Tag Point Module	301
Taxes	
invoicing	402, 409
labels	242, 243, 382
master catalog	154
purchase order	244, 386
reorder review	440
report	149
Requisition	375
service contract invoice	419
Thumbnails	
disabling	110
Timekeeping	
auto creation of timesheets	200
Timekeeping Authority Business Rule	
Employee Module	202
Employee Timekeeping Module	351
Leave Request Module	342
Timekeeping Charge Types Business Rule	
Employee Timekeeping Module	352
Timekeeping Comp Time Request Business Rule	
Employee Timekeeping Module	353
Timekeeping Copy Options Business Rule	
Employee Timekeeping Module	353
Timekeeping DTA Pay Code Business Rule (Custom)	81
Timekeeping DTA Reg Type Bus Rule (Custom)	81
Timekeeping Editchecks Business Rule	
Employee Timekeeping Module	354
Timekeeping Labor Earning Type Business Rule	
Employee Timekeeping Module	354
Timekeeping Leave Types Business Rule	
Leave Request Module	343
Timekeeping Module	346
Timekeeping Payroll Voucher	345
Transaction Logs	
Account Log	58
Auditing Log	58

Blanket Contract Log	58
Checkout Request Log	58
Component Log	58
Crew Activity Log	58
Direct Charges Log	58
Document Control Log	58
Inspection Log	58
Job Manager Log	58
Keys and Locks Log	58
Payroll Log	58
Property Log	58
Purchasing Log	58
Receiving Log	58
Runtime Entry Log	58
Service Contract Timesheet Log	58
Storeroom Transaction Log	58
Timekeeping Log	58
Work Order Activity Log	58

U

UDFs	122
UDFs - Auto Copy Across Modules Business Rule (General) 49	
Unit of Measurement Rule (General)	50
Update	289
Update Benchmark Work Order	
Fleet	289
Update Primary Vendor Business Rule	
Master Catalog Module	153
User Profile Module	117
User-Defined Fields Module	122

V

Validate Task Report Codes Business Rule	
Work Order Task Module	261
Variable Expense Codes Business Rule	
Checkout Request Module	427
Employee Timekeeping Module	356
Stock Checkout Module	432
Work Order Task Module	261
Vehicle Maintenance Reporting Standard	268, 290
Vendor (detail) View	
Request for Quotes Module	400
Vendor Code Structure Module	359
Vendor Module	360
Vendor Options Business Rule	
Vendor Module	362
Vendor Performance Attributes Business Rule	
Multi-Step Receiving Module	452

Vendor Module	363, 452	Workweek Schedule Module	336
Vendor Performance Ranges Business Rule		Workflow Groups Module	106, 125
Request for Quotes Module	399	Workweek Schedule Module	335
Vendor Module	364		
VeriSign	56		
VMRS	268, 290		
 W			
Warranty Claim Module	411		
Warranty Module	412		
Warranty Processing Rule			
Warranty Module	412		
Web Configuration Business Rule			
Attachment Modules	208		
Component ID Module	184		
Receiving Module	447		
Reports Administration Module	111		
WO Aging Business Rule			
Work Order Module	251		
WO Processing Rule			
Work Order Module	251		
Work	263		
Work Design Module	241		
Work Design Phase Business Rule			
Work Design Module	243		
Work Design Processing Business Rule			
Work Design Module	243		
Work Order Module	246		
Finishing Tasks	268		
Work Order Processing Business Rule			
Change Request Module	198		
Project/Subproject module	327		
Work Order Task Module	263		
Work Order Task Module	258		
Work Order Task Planning Business Rule			
Work Order Task Module	267		
Work Order Travel Time Business Rule			
Work Order Task Module	267		
Work Priority Defaults Business Rule			
Work Order Module	252		
Work Request Authority Business Rule			
Work Request Module	236		
Work Request Module	231		
Work Request Processing Business Rule			
Work Request Module	238		
Work Week Business Rule			
Daily Schedule Module	332		
Schedule Plan Module	338		