

Oracle® Solaris 11.4 Tunable Parameters Reference Manual

ORACLE®

Part No: E61034
August 2021

Part No: E61034

Copyright © 2000, 2021, Oracle and/or its affiliates.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, then the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Inside are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Epyc, and the AMD logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

This software or hardware and documentation may provide access to or information about content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services unless otherwise set forth in an applicable agreement between you and Oracle. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services, except as set forth in an applicable agreement between you and Oracle.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Access to Oracle Support

Oracle customers that have purchased support have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Diversity and Inclusion

Oracle is fully committed to diversity and inclusion. Oracle recognizes the influence of ethnic and cultural values and is working to remove language from our products and documentation that might be considered insensitive. While doing so, we are also mindful of the necessity to maintain compatibility with our customers' existing technologies and the need to ensure continuity of service as Oracle's offerings and industry standards evolve. Because of these technical constraints, our effort to remove insensitive terms is an ongoing, long-term process.

Référence: E61034

Copyright © 2000, 2021, Oracle et/ou ses affiliés.

Ce logiciel et la documentation qui l'accompagne sont protégés par les lois sur la propriété intellectuelle. Ils sont concédés sous licence et soumis à des restrictions d'utilisation et de divulgation. Sauf stipulation expresse de votre contrat de licence ou de la loi, vous ne pouvez pas copier, reproduire, traduire, diffuser, modifier, accorder de licence, transmettre, distribuer, exposer, exécuter, publier ou afficher le logiciel, même partiellement, sous quelque forme et par quelque procédé que ce soit. Par ailleurs, il est interdit de procéder à toute ingénierie inverse du logiciel, de le désassembler ou de le décompiler, excepté à des fins d'interopérabilité avec des logiciels tiers ou tel que prescrit par la loi.

Les informations fournies dans ce document sont susceptibles de modification sans préavis. Par ailleurs, Oracle Corporation ne garantit pas qu'elles soient exemptes d'erreurs et vous invite, le cas échéant, à lui en faire part par écrit.

Si ce logiciel, ou la documentation qui l'accompagne, est livré sous licence au Gouvernement des Etats-Unis, ou à quiconque qui aurait souscrit la licence de ce logiciel pour le compte du Gouvernement des Etats-Unis, la notice suivante s'applique :

U.S. GOVERNMENT END USERS: Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs) and Oracle computer documentation or other Oracle data delivered to or accessed by U.S. Government end users are "commercial computer software" or "commercial computer software documentation" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, the use, reproduction, duplication, release, display, disclosure, modification, preparation of derivative works, and/or adaptation of i) Oracle programs (including any operating system, integrated software, any programs embedded, installed or activated on delivered hardware, and modifications of such programs), ii) Oracle computer documentation and/or iii) other Oracle data, is subject to the rights and limitations specified in the license contained in the applicable contract. The terms governing the U.S. Government's use of Oracle cloud services are defined by the applicable contract for such services. No other rights are granted to the U.S. Government.

Ce logiciel ou matériel a été développé pour un usage général dans le cadre d'applications de gestion des informations. Ce logiciel ou matériel n'est pas conçu ni n'est destiné à être utilisé dans des applications à risque, notamment dans des applications pouvant causer un risque de dommages corporels. Si vous utilisez ce logiciel ou matériel dans le cadre d'applications dangereuses, il est de votre responsabilité de prendre toutes les mesures de secours, de sauvegarde, de redondance et autres mesures nécessaires à son utilisation dans des conditions optimales de sécurité. Oracle Corporation et ses affiliés déclinent toute responsabilité quant aux dommages causés par l'utilisation de ce logiciel ou matériel pour des applications dangereuses.

Oracle et Java sont des marques déposées d'Oracle Corporation et/ou de ses affiliés. Tout autre nom mentionné peut correspondre à des marques appartenant à d'autres propriétaires qu'Oracle.

Intel et Intel Inside sont des marques ou des marques déposées d'Intel Corporation. Toutes les marques SPARC sont utilisées sous licence et sont des marques ou des marques déposées de SPARC International, Inc. AMD, Epyc, et le logo AMD sont des marques ou des marques déposées d'Advanced Micro Devices. UNIX est une marque déposée de The Open Group.

Ce logiciel ou matériel et la documentation qui l'accompagne peuvent fournir des informations ou des liens donnant accès à des contenus, des produits et des services émanant de tiers. Oracle Corporation et ses affiliés déclinent toute responsabilité ou garantie expresse quant aux contenus, produits ou services émanant de tiers, sauf mention contraire stipulée dans un contrat entre vous et Oracle. En aucun cas, Oracle Corporation et ses affiliés ne sauraient être tenus pour responsables des pertes subies, des coûts occasionnés ou des dommages causés par l'accès à des contenus, produits ou services tiers, ou à leur utilisation, sauf mention contraire stipulée dans un contrat entre vous et Oracle.

Accessibilité de la documentation

Pour plus d'informations sur l'engagement d'Oracle pour l'accessibilité de la documentation, visitez le site Web Oracle Accessibility Program, à l'adresse : <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Accès aux services de support Oracle

Les clients Oracle qui ont souscrit un contrat de support ont accès au support électronique via My Oracle Support. Pour plus d'informations, visitez le site <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> ou le site <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> si vous êtes malentendant.

Contents

Using This Documentation	15
1 Overview of Oracle Solaris System Tuning	17
Tuning an Oracle Solaris System	17
/etc/system.d/ Directory Files	18
kmdb Utility	20
mdb Command	20
Tuning Format of Tunable Parameters Descriptions	21
Special Oracle Solaris tune and var Structures	22
Viewing Oracle Solaris System Configuration Information	23
sysdef Command	23
kstat Utility	23
kstat2 Utility	24
Oracle Solaris Observability Tools	24
2 Oracle Solaris Kernel Tunable Parameters	25
General Kernel and Memory Parameters	26
default_stksize Parameter	26
logevent_max_q_sz Parameter	27
lwp_default_stksize Parameter	27
noexec_user_stack Parameter	29
physmem Parameter	30
fsflush and Related Parameters	30
autoup Parameter	30
doiflush Parameter	32
dopageflush Parameter	32
fsflush Parameter	33

tune_t_fsflushr Parameter	34
Process-Sizing Parameters	34
max_nprocs Parameter	35
maxuprc Parameter	35
maxusers Parameter	36
ngroups_max Parameter	37
pidmax Parameter	38
reserved_procs Parameter	39
Paging-Related Parameters	39
desfree Parameter	41
fastscan Parameter	42
handspreadpages Parameter	43
lotsfree Parameter	43
maxpgio Parameter	44
min_percent_cpu Parameter	45
minfree Parameter	46
pageout_reserve Parameter	47
pages_before_pager Parameter	48
pages_pp_maximum Parameter	48
slowscan Parameter	49
throttlefree Parameter	50
tune_t_minarmem Parameter	51
Kernel Memory Allocator	51
kmem_flags Flag	52
kmem_stackinfo Variable	53
General Driver Parameters	54
SPARC: dax_stats_flags Flag	54
ddi_msix_alloc_limit Parameter	55
moddebug Parameter	56
Network Driver Parameters	57
IP Protocol Parameters in the Kernel	57
igb Parameters	59
ixgbe Parameters	60
General I/O Parameters	64
maxphys Parameter	65
rlim_fd_cur Parameter	65

rlim_fd_max Parameter	66
rlim_fd_sys Parameter	67
General File System Parameters	68
dnlc_dir_enable Parameter	68
dnlc_dir_max_size Parameter	68
dnlc_dir_min_size Parameter	69
dnlc_dircache_percent Parameter	69
ncsize Parameter	70
TMPFS Parameters	71
tmpfs:tmpfs_maxkmem Parameter	71
tmpfs:tmpfs_minfree Parameter	72
Pseudo Terminals	72
pt_cnt Parameter	73
pt_max_pty Parameter	74
pt_pctofmem Parameter	75
STREAMS Parameters	75
nstrpush Parameter	75
strmsgsz Parameter	76
strctlsz Parameter	77
System V Message Queues	77
System V Semaphores	77
Timer Behavior	78
hires_tick Parameter	78
timer_max Parameter	78
SPARC: Platform Specific Parameters	79
default_tsb_size Parameter	79
enable_tsb_rss_sizing Parameter	80
tsb_alloc_hiwater_factor Parameter	80
tsb_rss_factor Parameter	81
Locality Group Parameters	82
lgrp_mem_pset_aware Parameter	82
lpg_alloc_prefer Parameter	83
3 Oracle Solaris ZFS Tunable Parameters	85
Tuning ZFS Considerations	85
ZFS Memory Management Parameters	86

user_reserve_hint_pct ZFS Parameter	86
zfs_arc_min Parameter	87
zfs_arc_max Parameter	88
ZFS File-Level Prefetch	88
zfs_prefetch_disable Parameter	88
ZFS Device I/O Queue Depth	90
zfs_vdev_max_pending Parameter	90
Tuning ZFS When Using Flash Storage	91
Adding Flash Devices as ZFS Log or Cache Devices	92
Ensuring Proper Cache Flush Behavior for Flash and NVRAM Storage Devices	93
Tuning ZFS for Database Products	95
4 NFS Tunable Parameters	97
Tuning the NFS Environment	97
NFS Module Parameters	98
nfs:nfs_allow_preepoch_time Parameter	98
nfs:nfs_async_clusters Parameter	99
nfs:nfs3_async_clusters Parameter	100
nfs:nfs4_async_clusters Parameter	101
nfs:nfs_async_timeout Parameter	102
nfs:nfs3_bsize Parameter	102
nfs:nfs4_bsize Parameter	103
nfs:nfs_cots_timeo Parameter	104
nfs:nfs3_cots_timeo Parameter	105
nfs:nfs4_cots_timeo Parameter	105
nfs:nfs_disable_rmdir_cache Parameter	106
nfs:nfs_do_symlink_cache Parameter	107
nfs:nfs3_do_symlink_cache Parameter	108
nfs:nfs4_do_symlink_cache Parameter	108
nfs:nfs_dynamic Parameter	109
nfs:nfs3_dynamic Parameter	110
nfs:nfs3_jukebox_delay Parameter	110
nfs:nfs_lookup_neg_cache Parameter	111
nfs:nfs3_lookup_neg_cache Parameter	112
nfs:nfs4_lookup_neg_cache Parameter	113

nfs:nfs_max_threads Parameter	114
nfs:nfs3_max_threads Parameter	115
nfs:nfs4_max_threads Parameter	115
nfs:nfs3_max_transfer_size Parameter	116
nfs:nfs4_max_transfer_size Parameter	117
nfs:nfs3_max_transfer_size_clts Parameter	118
nfs:nfs3_max_transfer_size_cots Parameter	119
nfs:nacache Parameter	120
nfs:nfs_nra Parameter	120
nfs:nfs3_nra Parameter	121
nfs:nfs4_nra Parameter	122
nfs:nrnode Parameter	123
nfs:nfs3_pathconf_disable_cache Parameter	124
nfs:nfs_shrinkreaddir Parameter	124
nfs:nfs3_shrinkreaddir Parameter	125
nfs:nfs_write_error_interval Parameter	126
nfs:nfs_write_error_to_cons_only Parameter	127
NFS-Related SMF Configuration Parameters	127
server_authz_cache_refresh Parameter	128
netgroup_refresh Parameter	128
nfssrv Module Parameters	128
nfssrv:rfs_write_async Parameter	128
rpcmod Module Parameters	129
rpcmod:clnt_max_conns Parameter	129
rpcmod:clnt_idle_timeout Parameter	130
rpcmod:svc_idle_timeout Parameter	130
5 Internet Protocol Suite Tunable Parameters	133
Overview of Tuning IP Suite Parameters	133
IP Suite Parameter Validation	134
Internet Request for Comments	134
IP Tunable Parameters	134
_addr_per_if Parameter	134
_forwarding_src_routed Parameter (IPv4 or IPv6)	135
_icmp_err_interval and_icmp_err_burst Parameters	135

_policy_mask Parameter	136
_respond_to_echo_broadcast (IP) and _respond_to_echo_multicast Parameters (IPv4 or IPv6)	136
hoplimit Parameter (IPv6)	137
hostmodel Parameter (IPv4 or IPv6)	137
recv-multicast-scaling Parameter	138
send-redirects Parameter (IPv4 or IPv6)	139
ttl Parameter (IPv4)	139
IP Tunable Parameters Related to Duplicate Address Detection	140
IP Tunable Parameters With Additional Cautions	146
TCP Tunable Parameters	147
_conn_req_max_q Parameter	147
_conn_req_max_q0 Parameter	148
_conn_req_min Parameter	148
_deferred_ack_interval Parameter	149
_deferred_acks_max Parameter	149
_ipv4_ttl Parameter	150
_ipv6_hoplimit Parameter	150
_local_dack_interval Parameter	151
_local_dacks_max Parameter	151
_local_slow_start_initial Parameter	152
_rev_src_routes Parameter	152
_rst_sent_rate Parameter	152
_rst_sent_rate_enabled Parameter	153
_slow_start_after_idle Parameter	153
_slow_start_initial Parameter	154
_time_wait_interval Parameter	154
_tstamp_always Parameter	155
_wscale_always Parameter	155
cwnd-max Parameter	156
ecn Parameter	156
largest-anon-port Parameter	157
max-buf Parameter	157
recv-buf Parameter	158
sack Parameter	158
send-buf Parameter	159

smallest-anon-port Parameter	159
tcp_cwnd_normal Parameter	160
TCP Parameters With Additional Cautions	161
UDP Tunable Parameters	165
_ipv4_ttl Parameter	165
_ipv6_hoplimit Parameter	165
largest-anon-port Parameter	166
max-buf Parameter	166
recv-buf Parameter	167
send-buf Parameter	167
smallest-anon-port Parameter	168
SCTP Tunable Parameters	168
_addip_enabled Parameter	168
_cookie_life Parameter	169
_deferred_ack_interval Parameter	169
_heartbeat_interval Parameter	169
_ignore_path_mtu Parameter	170
_initial_mtu Parameter	170
_initial_out_streams Parameter	171
_initial_ssthresh Parameter	171
_ipv4_ttl Parameter	171
_ipv6_hoplimit Parameter	172
_maxburst Parameter	172
_max_in_streams Parameter	172
_max_init_retr Parameter	173
_new_secret_interval Parameter	173
_pa_max_retr Parameter	174
_pp_max_retr Parameter	174
_prsctp_enabled Parameter	175
_rto_initial Parameter	175
_rto_max Parameter	175
_rto_min Parameter	176
_shutack_wait_bound Parameter	176
_xmit_lowat Parameter	176
cwnd-max Parameter	177
largest_anon_port Parameter	177

max-buf Parameter	178
recv-buf Parameter	178
send-buf Parameter	179
smallest-anon-port Parameter	179
ICMP Tunable Parameters	180
_ipv4_ttl Parameter	180
_ipv6_hoplimit Parameter	180
Per-Route Metrics	181
6 System Facility Parameters	183
System Default Parameters	183
autofs Property	183
cron Facility	184
devfsadm File	184
fs File	184
ftp Facility	184
inetinit Facility	184
init Service	185
ipsec Facility	185
kbd Configuration Properties	185
keyserv Facility	186
login Facility	186
mpathd Facility	186
nfs Properties	187
nfslogd Log File	187
nss Facility	187
passwd Facility	187
su Facility	188
syslog Facility	188
tar Facility	188
telnetd Facility (Deprecated)	188
utmpd Daemon	188
A System Check Script	191
Confirming Flush Behavior on the System	191

Index 193

Using This Documentation

- **Overview** – Provides information about Oracle Solaris tunable parameters and how to configure these if the default values are insufficient for a specific customer setup.
- **Audience** – System administrators who might need to change kernel tunable parameters in certain situations.
- **Required knowledge** – Oracle Solaris or UNIX system administration experience and general file system administration experience.

Product Documentation Library

Documentation and resources for this product and related products are available at <http://www.oracle.com/pls/topic/lookup?ctx=E37838-01>.

Feedback

Provide feedback about this documentation at <http://www.oracle.com/goto/docfeedback>.

◆◆◆ **1** CHAPTER 1

Overview of Oracle Solaris System Tuning

This section provides overview information about the format of the tuning information in this manual. This section also describes the different ways to tune an Oracle Solaris system.

- [“Tuning an Oracle Solaris System” on page 17](#)
- [“Special Oracle Solaris tune and var Structures” on page 22](#)
- [“Viewing Oracle Solaris System Configuration Information” on page 23](#)

Tuning an Oracle Solaris System

As an operating system, Oracle Solaris adjusts easily to system load and thus requires minimal tuning. However, in certain cases, tuning might be necessary. This book provides details about the officially supported tuning options available for Oracle Solaris.

The Oracle Solaris kernel consists of a core portion, which is always loaded, and a number of loadable modules that are loaded as these modules are being referenced. Many kernel parameters listed in this manual are core parameters. However, a few parameters belong to loadable modules.

Note - Tuning system parameters is the least effective method to use to improve performance. Rather, improving and tuning the application, as well as adding more physical memory and balancing disk I/O patterns, are better options.

The tunable parameters described in this book can change from one Oracle Solaris release to the next. Publication of these tunable parameters does not preclude changes to the tunable parameters and their descriptions without notice.

The following table describes the different ways tunable parameters can be applied.

Apply Tunable Parameters in These Ways	For More Information
Set the parameter in a configuration file in the <code>/etc/system.d</code> directory.	“/etc/system.d/ Directory Files” on page 18

Apply Tunable Parameters in These Ways	For More Information
Use the kernel debugger (kmdb).	“kmdb Utility” on page 20
Use the modular debugger (mdb).	“mdb Command” on page 20
Use the <code>ipadm</code> command to set TCP/IP parameters.	Chapter 5, “Internet Protocol Suite Tunable Parameters”
Modify the <code>/etc/default</code> files.	Chapter 6, “System Facility Parameters”

`/etc/system.d/` Directory Files

The `/etc/system` file provides a static mechanism for adjusting the values of kernel parameters. Values specified in this file are read at boot time and then applied. No changes specified in the file take effect unless the system is rebooted.

However, to tune parameters, do **NOT** edit the `/etc/system` file. Instead, use files in the `/etc/system.d` directory. This method enables you to tune system parameters without directly manipulating the `/etc/system` file. The method consists of the following steps:

1. Create an empty file in the `/etc/system.d` directory.
2. Provide the file with a company specific name and indications of its contents.
3. In the file itself, add the customized setting for the tunable you are configuring.
As a first step, add only those tunables that are required by in-house or third-party applications. After baseline testing has been established, evaluate system performance to determine if additional tunable settings are required.

Files in the `/etc/system.d` directory are read at boot time and their contents are added to the `/etc/system` file. At the end of the boot process, the new configurations are applied to the system.

One pass is made to set all the values before the configuration parameters are calculated.

EXAMPLE 1 Setting a ZFS Parameter for a Specific System

The following entry sets the ZFS ARC maximum (`zfs_arc_max`) to 30 GB.

```
set zfs:zfs_arc_max = 0x78000000
```

Suppose that the name of your company is Widget, Inc. You would store this entry in the `/etc/system.d/widget:zfs` file. To apply the new `zfs_arc_max` setting, reboot the machine.

You can recover from an incorrect value by using one of the following approaches:

- Resetting the Parameter in the `/etc/system.d/file`

Remove the defective parameter setting from your configuration file in the `/etc/system.d` directory. At boot time, the `/etc/system` file is updated with the previous configurations which are then reapplied to the system.

- Using a Cloned Boot Environment

Before you introduce system parameter changes, clone the boot environment first.

```
# beadm create BE-clonename
```

Then, if your current BE becomes unusable after applying changes to `/etc/system`, reboot the system. From the x86 GRUB menu or SPARC boot menu, select the BE clone. After booting completes, you can optionally activate the BE clone to become the default BE to be used in subsequent system boots.

- Using File Copies

Make a copy of the `/etc/system` file before updating it with new parameters from configuration files in the `/etc/system.d` directory so that you can easily recover from incorrect value. For example:

```
# cp /etc/system /etc/system.good
```

If a value specified in the configuration file in `/etc/system.d` causes the system to become unbootable, you can recover with the following command:

```
ok boot -a
```

This command causes the system to ask for the name of various files used in the boot process. Press the Return key to accept the default values until the name of the `/etc/system` file is requested. When the `Name of system file [/etc/system]:` prompt appears, type the name of the good `/etc/system` file or `/dev/null`:

```
Name of system file [/etc/system]: /etc/system.good
```

If `/dev/null` is specified, this path causes the system to attempt to read from `/dev/null` for its configuration information. Because this file is empty, the system uses the default values. After the system is booted, the `/etc/system` file can be corrected.

For more information about system recovery, see [Troubleshooting System Administration Issues in Oracle Solaris 11.4](#).

kldb Utility

The `kldb` utility is an interactive kernel debugger with the same general syntax as the modular debugger (`mdb`). With this debugger, you can set breakpoints. When a breakpoint is reached, you can examine data or step through the execution of kernel code.



Caution - Because the `kldb` utility stops the kernel that is currently running, only use it if you are an expert user such as a kernel developer.

Do not use the `kldb` utility on production systems.

`kldb` can be loaded and unloaded on demand. You do not have to reboot the system to perform interactive kernel debugging, as was the case with the `kadb` utility.

For more information, see the [kldb\(1\)](#) man page.

mdb Command

The modular debugger, `mdb`, is the recommended post-mortem debugger for the kernel. This debugger also includes a number of desirable usability features such as command-line editing, command history, built-in output pager, syntax checking, and command pipelining. A programming API is available that enables a compilation of modules to perform desired tasks within the context of the debugger.

For more information, see the [Oracle Solaris Modular Debugger Guide](#) and the [mdb\(1\)](#) man page.

EXAMPLE 2 Using `mdb` to Display Information

Display a high-level view of a system's memory usage.

Note that the following command uses the `--kernel` option in place of the obsolescent `-k` option:

```
# mdb --kernel --unsafe-io-access
Loading modules: [ unix genunix specfs dtrace mac cpu.generic
cpu_ms.AuthenticAMD.15 uppc pcplusmp scsi_vhci zfs mpt sd ip
hook neti arp usba sockfs kssl qlc fctl stmf stmf_sbd md lofs
random idm fcp crypto cpc smbsrv nfs fcip spps ufs logindmux
ptm nsmb scu mpt_sas pmcs emlxs ]
> ::memstat
Page Summary                Pages                MB  %Tot
```

Kernel	160876	628	16%
ZFS File Data	303401	1185	30%
Anon	25335	98	2%
Exec and libs	1459	5	0%
Page cache	5083	19	1%
Free (cachelist)	6616	25	1%
Free (freelist)	510870	1995	50%
Total	1013640	3959	
Physical	1013639	3959	
> \$q			

When using either the `kldb` or `mdb` debugger, the module name prefix is not required. After a module is loaded, its symbols form a common name space with the core kernel symbols and any other previously loaded module symbols.

Tuning Format of Tunable Parameters Descriptions

This section describes the format for tuning Oracle Solaris parameters.

<i>Parameter</i>	The exact name of the tunable. Some parameters use the naming convention <i>module:parameter</i> to indicate that the parameter belongs to a loadable module. For example, <code>tmpfs:tmpfs_maxkmem</code> means that <code>tmpfs_maxkmem</code> is a parameter of the <code>tmpfs</code> module.
<i>Description</i>	Briefly describes what the parameter does or controls.
<i>Data Type</i>	Indicates the signed or unsigned short integer or long integer. A long integer is twice the width in bits as an integer. For example, an unsigned integer = 32 bits, an unsigned long integer = 64 bits.
<i>Units</i>	(Optional) Describes the unit type.
<i>Default</i>	Indicates the value that the system uses by default.
<i>Range</i>	Specifies the possible range allowed by system validation or the bounds of the data type. <ul style="list-style-type: none"> ■ <code>MAXINT</code> – A shorthand description for the maximum value of a signed integer (2,147,483,647)

	<ul style="list-style-type: none">■ MAXUINT – A shorthand description for the maximum value of an unsigned integer (4,294,967,295)
Dynamic?	Indicates whether the parameter can be configured on a running system with the mdb or kmdb debugger (Yes), or only during boot time initialization (No).
Validation	Checks that the system applies to the value of the variable either as specified in the <code>/etc/system</code> file or the default value, as well as when the validation is applied.
Implicit	(Optional) Provides unstated constraints that might exist on the parameter, especially in relation to other parameters.
When to Change	Explains why someone might want to change this value. Includes error messages or return codes.
Zone Configuration	Identifies whether the parameter can be set in an exclusive-IP zone or must be set in the global zone. None of the parameters can be set in shared-IP zones.
Commitment Level	Identifies the stability of the interface. Many of the parameters in this manual are still evolving and are classified as unstable. For more information, see the attributes(7) man page.

Special Oracle Solaris tune and var Structures

Oracle Solaris tunable parameters come in a variety of forms. The tune structure defined in the `/usr/include/sys/tuneable.h` file is the runtime representation of `tune_t_fsflushr`, `tune_t_minarmem`, and `tune_t_flkrec`. After the kernel is initialized, all references to these variables are found in the appropriate field of the tune structure.

The proper way to set parameters for this structure at boot time is to initialize the special parameter that corresponds to the desired field name. The system initialization process then loads these values into the tune structure.

A second structure into which various tunable parameters are placed is the var structure named `v`. You can find the definition of a var structure in the `/usr/include/sys/var.h` file. The runtime representation of variables such as `autoup` and `bufhwm` is stored here.



Caution - Do not change either the tune or v structure on a running system. Changing any field in these structures on a running system might cause a system panic.

Viewing Oracle Solaris System Configuration Information

Several tools are available to examine system configuration information. Some tools require superuser privilege. Other tools can be run by a non-privileged user. Every structure and data item can be examined with the kernel debugger by using `mdb` on a running system or by booting under `kmdb`.

For more information, see the [mdb\(1\)](#) or [kmdb\(1\)](#) man page.

sysdef Command

The `sysdef` command provides the values of memory and process resource limits, and portions of the tune and v structures. For example, the `sysdef` "Tunable Parameters" section from a SPARC T3-4 system with 500 GB of memory is as follows:

```
2206203904    maximum memory allowed in buffer cache (bufhwm)
65546        maximum number of processes (v.v_proc)
99           maximum global priority in sys class (MAXCLSYSPRI)
65541        maximum processes per user id (v.v_maxup)
30           auto update time limit in seconds (NAUTOUP)
25           page stealing low water mark (GPGSLO)
1            fsflush run rate (FSFLUSHR)
25           minimum resident memory for avoiding deadlock (MINARMEM)
25           minimum swapable memory for avoiding deadlock (MINASMEM)
```

For more information, see the [sysdef\(8\)](#) man page.

kstat Utility

kstats are data structures maintained by various kernel subsystems and drivers. They provide a mechanism for exporting data from the kernel to user programs without requiring that the program read kernel memory or have superuser privilege. For more information, see the [kstat\(8\)](#) and the [kstat\(3KSTAT\)](#) man pages.

kstat2 Utility

The `kstat2` utility shows values of kernel statistics (`kstats`). If you do not know the full name of the statistic you want, you can use a shell glob pattern or Perl Compatible Regular expression (PCRE). With options, you can show multiple statistic values over specified increments of time, and show the timestamp for each value, for example. For more information and examples, see the `kstat2(8)` man page. See also “[Oracle Solaris Observability Tools](#)” and “[Troubleshooting IPsec and IKE Semantic Errors](#)” in *Securing the Network in Oracle Solaris 11.4*.

Oracle Solaris Observability Tools

The Oracle Solaris System Web Interface shows `kstats` and many other statistics in a graphical form. The Observability Tools also shows relationships among statistics and shows values over time to help you diagnose problems with the system. For more information, see [Using Oracle Solaris 11.4 StatsStore and System Web Interface](#).

Oracle Solaris Kernel Tunable Parameters

This chapter describes most of the Oracle Solaris kernel tunable parameters.

- [“General Kernel and Memory Parameters” on page 26](#)
- [“fsflush and Related Parameters” on page 30](#)
- [“Process-Sizing Parameters” on page 34](#)
- [“Paging-Related Parameters” on page 39](#)
- [“Kernel Memory Allocator” on page 51](#)
- [“General Driver Parameters” on page 54](#)
- [“Network Driver Parameters” on page 57](#)
- [“General I/O Parameters” on page 64](#)
- [“General File System Parameters” on page 68](#)
- [“TMPFS Parameters” on page 71](#)
- [“Pseudo Terminals” on page 72](#)
- [“STREAMS Parameters” on page 75](#)
- [“System V Message Queues” on page 77](#)
- [“System V Semaphores” on page 77](#)
- [“Timer Behavior” on page 78](#)
- [“Platform Specific Parameters” on page 79](#)
- [“Locality Group Parameters” on page 82](#)

For other types of tunable parameters, refer to the following:

- [Oracle Solaris ZFS tunables parameters – Chapter 3, “Oracle Solaris ZFS Tunable Parameters”](#)
- [NFS tunable parameters – Chapter 4, “NFS Tunable Parameters”](#)
- [Internet Protocol Suite tunable parameters – Chapter 5, “Internet Protocol Suite Tunable Parameters”](#)
- [System facility tunable parameters – Chapter 6, “System Facility Parameters”](#)

General Kernel and Memory Parameters

This section describes general kernel parameters that are related to physical memory and stack configuration. For ZFS-related memory parameters, see [Chapter 3, “Oracle Solaris ZFS Tunable Parameters”](#).

default_stksize Parameter

Description	Specifies the default stack size of all threads. No thread can be created with a stack size smaller than <code>default_stksize</code> . If <code>default_stksize</code> is set, it overrides <code>lwp_default_stksize</code> . See also “lwp_default_stksize Parameter” on page 27 .
Data Type	Integer
Default	<ul style="list-style-type: none">4 x <code>PAGESIZE</code> on SPARC systems with sun4v processors5 x <code>PAGESIZE</code> on x64 systems
Range	Minimum is the default values: <ul style="list-style-type: none">4 x <code>PAGESIZE</code> on SPARC systems with sun4v processors5 x <code>PAGESIZE</code> on x64 systems Maximum is 32 times the default value.
Units	Bytes in multiples of the value returned by the <code>getpagesize</code> parameter. For more information, see the getpagesize(3C) man page.
Dynamic?	Yes. Affects threads created after the variable is changed.
Validation	Must be greater than or equal to 8192 and less than or equal to 262,144 (256 x 1024). Also must be a multiple of the system page size. If these conditions are not met, the following message is displayed: <pre>Illegal stack size, Using N</pre> The value of <i>N</i> is the default value of <code>default_stksize</code> .
When to Change	When the system panics because it has run out of stack space. The best solution for this problem is to determine why the system is running out of space and then make a correction. Increasing the default stack size means that almost every kernel thread will have a larger stack, resulting in increased kernel memory

consumption for no good reason. Generally, that space will be unused. The increased consumption means other resources that are competing for the same pool of memory will have the amount of space available to them reduced, possibly decreasing the system's ability to perform work. Among the side effects is a reduction in the number of threads that the kernel can create. This solution should be treated as no more than an interim workaround until the root cause is remedied.

Commitment Level Unstable

logevent_max_q_sz Parameter

Description	Maximum number of system events allowed to be queued and waiting for delivery to the syseventd daemon. Once the size of the system event queue reaches this limit, no other system events are allowed on the queue.
Data Type	Integer
Default	5000
Range	0 to MAXINT
Units	System events
Dynamic?	Yes
Validation	The system event framework checks this value every time a system event is generated by <code>ddi_log_sysevent</code> and <code>sysevent_post_event</code> . For more information, see the ddi_log_sysevent(9F) and sysevent_post_event(3SYSEVENT) man pages.
When to Change	When error log messages indicate that a system event failed to be logged, generated, or posted.
Commitment Level	Unstable

lwp_default_stksize Parameter

Description	Specifies the default value of the stack size to be used when a kernel thread is created, and when the calling routine does not provide an
-------------	--

	explicit size to be used. Any stack size that you specify is increased by a one-page redzone.
Data Type	Integer
Default	<ul style="list-style-type: none"> ■ Default SPARC stack size is 3 pages (3 x 8,192 = 24,576) + 8 KB redzone ■ Default x64 stack size is 5 pages (5 x 4,096 = 20,480) + 4 KB redzone
Range	<p>Minimum is the default values:</p> <ul style="list-style-type: none"> ■ 3 x PAGESIZE on SPARC systems ■ 5 x PAGESIZE on x64 systems <p>Maximum is 32 times the default value.</p>
Units	Bytes in multiples of the value returned by the <code>getpagesize</code> parameter. For more information, see the getpagesize(3C) man page.
Dynamic?	Yes. Affects threads created after the variable is changed.
Validation	<p>Must be greater than or equal to 8192 and less than or equal to 262,144 (256 x 1024). Also must be a multiple of the system page size. If these conditions are not met, the following message is displayed:</p> <pre>Illegal stack size, Using N</pre> <p>The value of <i>N</i> is the default value of <code>lwp_default_stksize</code>.</p>
When to Change	<p>When the system panics because it has run out of stack space. The best solution for this problem is to determine why the system is running out of space and then make a correction.</p> <p>Increasing the default stack size means that almost every kernel thread will have a larger stack, resulting in increased kernel memory consumption for no good reason. Generally, that space will be unused. The increased consumption means other resources that are competing for the same pool of memory will have the amount of space available to them reduced, possibly decreasing the system's ability to perform work. Among the side effects is a reduction in the number of threads that the kernel can create. This solution should be treated as no more than an interim workaround until the root cause is remedied.</p>
Commitment Level	Unstable

noexec_user_stack Parameter

Note - Although `noexec_user_stack` is still operational, this parameter is deprecated in this Oracle Solaris release. Use the `nxheap` and `nxstack` security extensions instead. You can control and configure Oracle Solaris extensions at the system level and at the process level with the `sxadm` command.

For procedures and examples that show the use of `nxheap` and `nxstack`, see [“Protecting the Process Heap and Executable Stacks From Compromise”](#) in *Securing Systems and Attached Devices in Oracle Solaris 11.4*.

For more information about the `sxadm` command, see the `sxadm(8)` man page.

For guidelines to secure and harden Oracle Solaris, see [Oracle Solaris 11.4 Security and Hardening Guidelines](#).

Description	<p>Enables the stack to be marked as nonexecutable, which helps make buffer-overflow attacks more difficult.</p> <p>An Oracle Solaris system running a 64-bit kernel makes the stacks of all 64-bit applications nonexecutable by default. Setting this parameter is necessary to make the stacks of all 32-bit applications nonexecutable by default if they weren't linked with the <code>nxstack</code> security extensions flag. This parameter, together with <code>noexec_user_stack_log</code>, can be set in a file in the <code>/etc/system.d</code> directory. See “Protecting the Process Heap and Executable Stacks From Compromise” in <i>Securing Systems and Attached Devices in Oracle Solaris 11.4</i></p>
Data Type	Signed integer
Default	0 (disabled)
Range	0 (disabled) or 1 (enabled)
Units	Toggle (on/off)
Dynamic?	Yes. Does not affect currently running processes, only processes created after the value is set.
Validation	None
When to Change	Should be enabled at all times unless applications are deliberately placing executable code on the stack without using <code>mprotect</code> to make the stack executable. For more information, see the <code>mprotect(2)</code> man page.

Commitment Level Unstable

physmem Parameter

Description	Modifies the system's configuration of the number of physical pages of memory after the Oracle Solaris OS and firmware are accounted for.
Data Type	Unsigned long
Default	Number of usable pages of physical memory available on the system, not counting the memory where the core kernel and data are stored
Range	1 to amount of physical memory on system
Units	Pages
Dynamic?	No
Validation	None
When to Change	Whenever you want to test the effect of running the system with less physical memory. Because this parameter does <i>not</i> take into account the memory used by the core kernel and data, as well as various other data structures allocated early in the startup process, the value of <code>physmem</code> should be less than the actual number of pages that represent the smaller amount of memory.
Commitment Level	Unstable

fsflush and Related Parameters

This section describes `fsflush` and related tunables.

autoup Parameter

Description	Along with <code>tune_t_flushr</code> , <code>autoup</code> controls the amount of memory examined for dirty pages in each invocation and frequency of file system synchronizing operations.
-------------	--

	<p>The value of <code>autoup</code> is also used to control whether a buffer is written out from the free list. Buffers marked with the <code>B_DELWRI</code> flag (which identifies file content pages that have changed) are written out whenever the buffer has been on the list for longer than <i>autoup</i> seconds. Increasing the value of <code>autoup</code> keeps the buffers in memory for a longer time.</p>
Data Type	Signed integer
Default	30
Range	1 to MAXINT
Units	Seconds
Dynamic?	No
Validation	If <code>autoup</code> is less than or equal to zero, it is reset to 30 and a warning message is displayed. This check is done only at boot time.
Implicit	<p><code>autoup</code> should be an integer multiple of <code>tune_t_fsflushr</code>. At a minimum, <code>autoup</code> should be at least 6 times the value of <code>tune_t_fsflushr</code>. If not, excessive amounts of memory are scanned each time <code>fsflush</code> is invoked.</p> <p>The total system pages multiplied by <code>tune_t_fsflushr</code> should be greater than or equal to <code>autoup</code> to cause memory to be checked if <code>dopageflush</code> is non-zero.</p>
When to Change	<p>Here are several potential situations for changing <code>autoup</code>, <code>tune_t_fsflushr</code>, or both:</p> <ul style="list-style-type: none"> ■ Systems with large amounts of memory – In this case, increasing <code>autoup</code> reduces the amount of memory scanned in each invocation of <code>fsflush</code>. ■ Systems with minimal memory demand – Increasing both <code>autoup</code> and <code>tune_t_fsflushr</code> reduces the number of scans made. <code>autoup</code> should be increased also to maintain the current ratio of <code>autoup</code> / <code>tune_t_fsflushr</code>. ■ Systems with large numbers of transient files (for example, mail servers or software build systems) – If large numbers of files are created and then deleted, <code>fsflush</code> might unnecessarily write data pages for those files to disk.
Commitment Level	Unstable

doiflush Parameter

Description	Controls whether file system metadata syncs will be executed during fsflush invocations. This synchronization is done every N th invocation of fsflush where $N = (\text{autoup} / \text{tune_t_fsflushr})$. Because this algorithm is integer division, if tune_t_fsflushr is greater than autoup, a synchronization is done on every invocation of fsflush because the code checks to see if its iteration counter is greater than or equal to N . Note that N is computed once on invocation of fsflush. Later changes to tune_t_fsflushr or autoup have no effect on the frequency of synchronization operations.
Data Type	Signed integer
Default	1 (enabled)
Range	0 (disabled) or 1 (enabled)
Units	Toggle (on/off)
Dynamic?	Yes
Validation	None
When to Change	<p>When files are frequently modified over a period of time and the load caused by the flushing perturbs system behavior.</p> <p>Files whose existence, and therefore consistency of state, does not matter if the system reboots are better kept in a TMPFS file system (for example, /tmp). Inode traffic can be reduced on systems by using the mount -noatime option. This option eliminates inode updates when the file is accessed.</p> <p>For a system engaged in realtime processing, you might want to disable this option and use explicit application file synchronizing to achieve consistency.</p>
Commitment Level	Unstable

dopageflush Parameter

Description	Controls whether memory is examined for modified pages during fsflush invocations. In each invocation of fsflush, the number of
-------------	---

physical memory pages in the system is determined. This number might have changed because of a dynamic reconfiguration operation. Each invocation scans by using this algorithm: total number of pages x `tune_t_fsflushr / autoup` pages

Data Type	Signed integer
Default	1 (enabled)
Range	0 (disabled) or 1 (enabled)
Units	Toggle (on/off)
Dynamic?	Yes
Validation	None
When to Change	If the system page scanner rarely runs, which is indicated by a value of 0 in the <code>sr</code> column of <code>vmstat</code> output.
Commitment Level	Unstable

fsflush Parameter

The system daemon, `fsflush`, runs periodically to do three main tasks:

1. On every invocation, `fsflush` flushes dirty file system pages over a certain age to disk.
2. On every invocation, `fsflush` examines a portion of memory and causes modified pages to be written to their backing store. Pages are written if they are modified and if they do not meet one of the following conditions:
 - Pages are kernel page
 - Pages are free
 - Pages are locked
 - Pages are associated with a swap device
 - Pages are currently involved in an I/O operation

The net effect is to flush pages from files that are mapped with `mmap` with write permission and that have actually been changed.

Pages are flushed to backing store but left attached to the process using them. This will simplify page reclamation when the system runs low on memory by avoiding delay for writing the page to backing store before claiming it, if the page has not been modified since the flush.

3. `fsflush` writes file system metadata to disk. This write is done every n th invocation, where n is computed from various configuration variables. See “[tune_t_fsflushr Parameter](#)” on page 34 and “[autoup Parameter](#)” on page 30 for details.

The following features are configurable:

- Frequency of invocation (`tune_t_fsflushr`)
- Whether memory scanning is executed (`dopageflush`)
- Whether file system data flushing occurs (`doiflush`)
- The frequency with which file system data flushing occurs (`autoup`)

For most systems, memory scanning and file system metadata synchronizing are the dominant activities for `fsflush`. Depending on system usage, memory scanning can be of little use or consume too much CPU time.

tune_t_fsflushr Parameter

Description	Specifies the number of seconds between <code>fsflush</code> invocations
Data Type	Signed integer
Default	1
Range	1 to MAXINT
Units	Seconds
Dynamic?	No
Validation	If the value is less than or equal to zero, the value is reset to 1 and a warning message is displayed. This check is done only at boot time.
When to Change	See the <code>autoup</code> parameter.
Commitment Level	Unstable

Process-Sizing Parameters

Several parameters (or variables) are used to control the number of processes that are available on the system and the number of processes that an individual user can create. The foundation parameter is `maxusers`. This parameter drives the values assigned to `max_nprocs` and `maxuprc`.

max_nprocs Parameter

Description	<p>Specifies the maximum number of processes that can be created on a system. Includes system processes and user processes. Any value specified in <i>/etc/system.d/file</i> is used in the computation of <code>maxuprc</code>. This value is also used in determining the size of several other system data structures. Other data structures where this parameter plays a role are as follows:</p> <ul style="list-style-type: none"> ▪ Determining the size of the directory name lookup cache (if <code>ncsize</code> is not specified) ▪ Verifying that the amount of memory used by configured system V semaphores does not exceed system limits ▪ Configuring Hardware Address Translation resources for x86 platforms
Data Type	Signed integer
Default	<p>$10 + (16 \times \text{maxusers})$ if <code>maxusers</code> is set in <i>/etc/system.d/file</i></p> <p>The larger of 30,000 or $10 + (128 \times \text{number of CPUs})$, if <code>maxusers</code> is not set in <i>/etc/system.d/file</i></p>
Range	26 to value of <code>maxpid</code>
Dynamic?	No
Validation	Yes. If the value exceeds <code>maxpid</code> , it is set to <code>maxpid</code> .
When to Change	Changing this parameter is one of the steps necessary to enable support for more than 30,000 processes on a system.
Commitment Level	Unstable

maxuprc Parameter

Description	Specifies the maximum number of processes that can be created on a system by any one user.
Data Type	Signed integer
Default	<code>max_nprocs - reserved_procs</code>

Range	1 to <code>max_nprocs - reserved_procs</code>
Units	Processes
Dynamic?	No
Validation	Yes. This value is compared to <code>max_nprocs - reserved_procs</code> and set to the smaller of the two values.
When to Change	When you want to specify a hard limit for the number of processes a user can create that is less than the default value of however many processes the system can create. Attempting to exceed this limit generates the following warning messages on the console or in the messages file: out of per-user processes for uid <i>N</i>
Commitment Level	Unstable

maxusers Parameter

Description	Originally, <code>maxusers</code> defined the number of logged in users the system could support. When a kernel was generated, various tables were sized based on this setting. Current Oracle Solaris releases do much of its sizing based on the amount of memory on the system. Thus, much of the past use of <code>maxusers</code> has changed. The following list identifies subsystems that are still derived from <code>maxusers</code> : <ul style="list-style-type: none"> ■ The maximum number of processes on the system ■ The number of quota structures held in the system ■ The size of the directory name look-up cache (DNLC)
Data Type	Signed integer
Default	Lesser of the amount of memory in MB or 2048, and the greater of that value and <code>nCPUs x 8</code>
Range	1 to the greater of 2048 or <code>nCPUs x 8</code> , based on the size of physical memory, if not set in <code>/etc/system.d/file</code> 1 to the greater of 4096 or the <code>nCPUs x 8</code> , if set in <code>/etc/system.d/file</code>
Units	Users

Dynamic?	No. After computation of dependent parameters is done, <code>maxusers</code> is never referenced again.
Validation	If the value is greater than the maximum allowed, it is reset to the maximum. A message to that effect is displayed.
When to Change	<p>When the default number of user processes derived by the system is too low. This situation is evident when the following message displays on the system console:</p> <pre>out of processes</pre> <p>You might also change this parameter when the default number of processes is too high, as in these situations:</p> <ul style="list-style-type: none"> ■ Database servers that have a lot of memory and relatively few running processes can save system memory when the default value of <code>maxusers</code> is reduced. ■ If file servers have a lot of memory and few running processes, you might reduce this value. However, you should explicitly set the size of the DNLC. See “ncsize Parameter” on page 70.
Commitment Level	Unstable

`ngroups_max` Parameter

Description	Specifies the maximum number of supplemental groups per process.
Data Type	Signed integer
Default	1024
Range	16 to 1024
Units	Groups
Dynamic?	No
Validation	Yes. If <code>ngroups_max</code> is set to an invalid value, it is automatically reset to the closest legal value. For example, if it is set to less than zero, it is reset to 0. If it is set to greater than 1024, it is reset to 1024.
When to Change	Review the following considerations if you are using NFS AUTH_SYS authentication and you want to increase the default <code>ngroups_max</code> value:

1. If `ngroups_max` is set to 16 or if the NFS client's `AUTH_SYS` credential that is provided has 15 or fewer groups, the client's group information is used.
2. If `ngroups_max` is set to greater than 16 **and** the NFS client's `AUTH_SYS` credential from the name server contains exactly 16 groups, the maximum allowed, the NFS server consults the name server and matches the client's UID to a user name. Then, the name server computes a list of groups to which the user belongs.

Commitment Level Unstable

pidmax Parameter

Description	<p>Specifies the value of the largest possible process ID.</p> <p><code>pidmax</code> sets the value for the <code>maxpid</code> variable. Once <code>maxpid</code> is set, <code>pidmax</code> is ignored. <code>maxpid</code> is used elsewhere in the kernel to determine the maximum process ID and for validation checking.</p> <p>Any attempts to set <code>maxpid</code> by adding an entry to a file in the <code>/etc/system.d</code> directory have no effect.</p>
Data Type	Signed integer
Default	30,000
Range	5 to 999,999
Units	Processes
Dynamic?	No. Used only at boot time to set the value of <code>pidmax</code> .
Validation	Yes. Value is compared to the value of <code>reserved_procs</code> and 999,999. If less than <code>reserved_procs</code> or greater than 999,999, the value is set to 999,999.
Implicit	<code>max_nprocs</code> range checking ensures that <code>max_nprocs</code> is always less than or equal to this value.
When to Change	Required to enable support for more than 30,000 processes on a system. See also “max_nprocs Parameter” on page 35 .

Commitment Level Unstable

reserved_procs Parameter

Description	Specifies the number of system process slots to be reserved in the process table for processes with a UID of root (0). For example, <code>fsflush</code> has a UID of root (0).
Data Type	Signed integer
Default	5
Range	5 to MAXINT
Units	Processes
Dynamic?	No. Not used after the initial parameter computation.
Validation	Any <code>/etc/system.d/file</code> setting is honored.
Commitment Level	Unstable
When to Change	Consider increasing to 10 + the normal number of UID 0 (root) processes on system. This setting provides some cushion should it be necessary to obtain a root shell when the system is otherwise unable to create user-level processes.

Paging-Related Parameters

The Oracle Solaris OS uses a demand paged virtual memory system. As the system runs, pages are brought into memory as needed. When memory becomes occupied above a certain threshold and demand for memory continues, paging begins. Paging goes through several levels that are controlled by certain parameters.

The general paging algorithm is as follows:

- A memory deficit is noticed. The page scanner thread runs and begins to walk through memory. A two-step algorithm is employed:
 1. A page is marked as unused.

2. If still unused after a time interval, the page is viewed as a subject for reclaim.

If the page has been modified, a request is made to the pageout thread to schedule the page for I/O. Also, the page scanner continues looking at memory. Pageout causes the page to be written to the page's backing store and placed on the free list. When the page scanner scans memory, no distinction is made as to the origin of the page. The page might have come from a data file, or it might represent a page from an executable's text, data, or stack.

- As memory pressure on the system increases, the algorithm becomes more aggressive in the pages it will consider as candidates for reclamation and in how frequently the paging algorithm runs. (For more information, see “[fastscan Parameter](#)” on page 42 and “[slowscan Parameter](#)” on page 49.) As available memory falls between the range `lotsfree` and `minfree`, the system linearly increases the amount of memory scanned in each invocation of the pageout thread from the value specified by `slowscan` to the value specified by `fastscan`. The system uses the `desfree` parameter to control a number of decisions about resource usage and behavior.

The system initially constrains itself to use no more than 4 percent of one CPU for pageout operations. As memory pressure increases, the amount of CPU time consumed in support of pageout operations linearly increases until a maximum of 80 percent of one CPU is consumed. The algorithm looks through some amount of memory between `slowscan` and `fastscan`, then stops when one of the following occurs:

- Enough pages have been found to satisfy the memory shortfall.
- The planned number of pages have been looked at.
- Too much time has elapsed.

If a memory shortfall is still present when pageout finishes its scan, another scan is scheduled for 1/4 second in the future.

The configuration mechanism of the paging subsystem was changed. Instead of depending on a set of predefined values for `fastscan`, `slowscan`, and `handspreadpages`, the system determines the appropriate settings for these parameters at boot time. Setting any of these parameters in files in the `/etc/system.d` directory can cause the system to use less than optimal values.



Caution - Remove all tuning of the VM system from files in the `/etc/system.d` directory. Run with the default settings and determine if it is necessary to adjust any of these parameters. Do not set either `cachefree` or `priority_paging`.

Dynamic reconfiguration (DR) for CPU and memory is supported. A system in a DR operation that involves the addition or deletion of memory recalculates values for the relevant parameters, unless the parameter has been explicitly set in `/etc/system.d/file`. In that case, the value specified in `/etc/system.d/file` is used, unless a constraint on the value of the variable has been violated. In this case, the value is reset.

desfree Parameter

Description	Specifies the preferred amount of memory to be free at all times on the system.
Data Type	Unsigned integer
Default	<code>lotsfree / 2</code>
Range	<p>The minimum value is 256 KB or 1/128th of physical memory, whichever is greater, expressed as pages using the page size returned by <code>getpagesize</code>.</p> <p>The maximum value is the number of physical memory pages. The maximum value should be no more than 15 percent of physical memory. The system does not enforce this range other than that described in the Validation section.</p>
Units	Pages
Dynamic?	Yes, unless dynamic reconfiguration operations that add or delete memory occur. At that point, the value is reset to the value provided in <code>/etc/system.d/file</code> or calculated from the new physical memory value.
Validation	If <code>desfree</code> is greater than <code>lotsfree</code> , <code>desfree</code> is set to <code>lotsfree / 2</code> . No message is displayed.
Implicit	The relationship of <code>lotsfree</code> being greater than <code>desfree</code> , which is greater than <code>minfree</code> , should be maintained at all times.
Side Effects	<p>Several side effects can arise from increasing the value of this parameter. When the new value nears or exceeds the amount of available memory on the system, the following can occur:</p> <ul style="list-style-type: none"> ■ Asynchronous I/O requests are not processed, unless available memory exceeds <code>desfree</code>. Increasing the value of <code>desfree</code> can result in rejection of requests that otherwise would succeed. ■ NFS asynchronous writes are executed as synchronous writes. ■ The swapper is awakened earlier, and the behavior of the swapper is biased towards more aggressive actions. ■ The system might not preload (prefault) as many executable pages as possible into the system. This side effect results in applications potentially running slower than they otherwise would.

When to Change	For systems with relatively static workloads and large amounts of memory, lower this value. The minimum acceptable value is 256 KB, expressed as pages using the page size returned by <code>getpagesize</code> .
Commitment Level	Unstable

fastscan Parameter

Description	Defines the maximum number of pages per second that the system looks at when memory pressure is highest.
Data Type	Signed integer
Default	<p>The <code>fastscan</code> default value is set in one of the following ways:</p> <ul style="list-style-type: none">▪ The <code>fastscan</code> value set in <code>/etc/system.d/file</code> is used.▪ The <code>maxfastscan</code> value set in <code>/etc/system.d/file</code> is used.▪ If neither <code>fastscan</code> nor <code>maxfastscan</code> is set in <code>/etc/system.d/file</code>, <code>fastscan</code> is set to 64 MB when the system is booted. Then, after the system is booted for a few minutes, the <code>fastscan</code> value is set to the number of pages that the scanner can scan in one second using 10% of a CPU. <p>In all three cases, if the derived value is more than half the memory in the system, the <code>fastscan</code> value is capped at the value of half the memory in the system.</p>
Range	64 MB to half the system's physical memory
Units	Pages
Dynamic?	Yes, unless dynamic reconfiguration operations that add or delete memory occur. At that point, the value is reset to the value provided by <code>/etc/system.d/file</code> or calculated from the new physical memory value.
Validation	The maximum value is the lesser of 64 MB and 1/2 of physical memory.
When to Change	When more aggressive scanning of memory is preferred during periods of memory shortfall, especially when the system is subject to periods of intense memory demand or when performing heavy file I/O.
Commitment Level	Unstable

handspreadpages Parameter

Description	The Oracle Solaris OS uses a two-handed clock algorithm to look for pages that are candidates for reclaiming when memory is low. The first hand of the clock walks through memory marking pages as unused. The second hand walks through memory some distance after the first hand, checking to see if the page is still marked as unused. If so, the page is subject to being reclaimed. The distance between the first hand and the second hand is <code>handspreadpages</code> .
Data Type	Unsigned long
Default	<code>fastscan</code>
Range	1 to maximum number of physical memory pages on the system.
Units	Pages
Dynamic?	Yes. This parameter requires that the kernel <code>reset_hands</code> parameter also be set to a non-zero value. Once the new value of <code>handspreadpages</code> has been recognized, <code>reset_hands</code> is set to zero.
Validation	The value is set to the lesser of either the amount of physical memory and the <code>handspreadpages</code> <i>value</i> .
When to Change	When you want to increase the amount of time that pages are potentially resident before being reclaimed. Increasing this value increases the separation between the hands, and therefore, the amount of time before a page can be reclaimed.
Commitment Level	Unstable

lotsfree Parameter

Description	Serves as the initial trigger for system paging to begin. When this threshold is crossed, the page scanner wakes up to begin looking for memory pages to reclaim.
Data Type	Unsigned long
Default	The greater of 1/64th of physical memory or 512 KB

Range	<p>The minimum value is 512 KB or 1/64th of physical memory, whichever is greater, expressed as pages using the page size returned by <code>getpagesize</code>. For more information, see the getpagesize(3C) man page.</p> <p>The maximum value is the number of physical memory pages. The maximum value should be no more than 30 percent of physical memory. The system does not enforce this range, other than that described in the Validation section.</p>
Units	Pages
Dynamic?	Yes, but dynamic changes are lost if a memory-based DR operation occurs.
Validation	If <code>lotsfree</code> is greater than the amount of physical memory, the value is reset to the default.
Implicit	The relationship of <code>lotsfree</code> being greater than <code>desfree</code> , which is greater than <code>minfree</code> , should be maintained at all times.
When to Change	<p>When demand for pages is subject to sudden sharp spikes, the memory algorithm might be unable to keep up with demand. One workaround is to start reclaiming memory at an earlier time. This solution gives the paging system some additional margin.</p> <p>A rule of thumb is to set this parameter to 2 times what the system needs to allocate in a few seconds. This parameter is workload dependent. A DBMS server can probably work fine with the default settings. However, you might need to adjust this parameter for a system doing heavy file system I/O.</p> <p>For systems with relatively static workloads and large amounts of memory, lower this value. The minimum acceptable value is 512 KB, expressed as pages using the page size returned by <code>getpagesize</code>.</p>
Commitment Level	Unstable

maxpgio Parameter

Description	Defines the maximum number of page I/O requests that can be queued by the paging system. This number is divided by 4 to get the actual maximum number used by the paging system. This parameter is used to throttle the number of requests as well as to control process swapping.
-------------	--

Data Type	Signed integer
Default	400
Range	1 to a variable maximum that depends on the system architecture, but mainly by the I/O subsystem, such as the number of controllers, disks, and disk swap size
Units	I/Os
Dynamic?	No
Validation	None
Implicit	The maximum number of I/O requests from the pager is limited by the size of a list of request buffers, which is currently sized at 256.
When to Change	Increase this parameter to page out memory faster. A larger value might help to recover faster from memory pressure if more than one swap device is configured or if the swap device is a striped device. Note that the existing I/O subsystem should be able to handle the additional I/O load. Also, increased swap I/O could degrade application I/O performance if the swap partition and application files are on the same disk.
Commitment Level	Unstable

min_percent_cpu Parameter

Description	Defines the minimum percentage of CPU that pageout can consume. This parameter is used as the starting point for determining the maximum amount of time that can be consumed by the page scanner.
Data Type	Signed integer
Default	4
Range	1 to 80
Units	Percentage
Dynamic?	Yes

Validation	None
When to Change	Increasing this value on systems with multiple CPUs and lots of memory, which are subject to intense periods of memory demand, enables the pager to spend more time attempting to find memory.
Commitment Level	Unstable

minfree Parameter

Description	Specifies the minimum acceptable memory level. When memory drops below this number, the system biases allocations toward allocations necessary to successfully complete pageout operations or to swap processes completely out of memory. Either allocation denies or blocks other allocation requests.
Data Type	Unsigned integer
Default	<code>desfree / 2</code>
Range	<p>The minimum value is 128 KB or 1/256th of physical memory, whichever is greater, expressed as pages using the page size returned by <code>getpagesize</code>.</p> <p>The maximum value is the number of physical memory pages. The maximum value should be no more than 7.5 percent of physical memory. The system does not enforce this range other than that described in the Validation section.</p>
Units	Pages
Dynamic?	Yes, unless dynamic reconfiguration operations that add or delete memory occur. At that point, the value is reset to the value provided in <code>/etc/system.d/file</code> or calculated from the new physical memory value.
Validation	If <code>minfree</code> is greater than <code>desfree</code> , <code>minfree</code> is set to <code>desfree / 2</code> . No message is displayed.
Implicit	The relationship of <code>lotsfree</code> being greater than <code>desfree</code> , which is greater than <code>minfree</code> , should be maintained at all times.
When to Change	The default value is generally adequate. For systems with relatively static workloads and large amounts of memory, lower this value. The

minimum acceptable value is 128 KB, expressed as pages using the page size returned by `getpagesize`.

Commitment Level Unstable

pageout_reserve Parameter

Description	Specifies the number of pages reserved for the exclusive use of the pageout or scheduler threads. When available memory is less than this value, nonblocking allocations are denied for any processes other than pageout or the scheduler. Pageout needs to have a small pool of memory for its use so it can allocate the data structures necessary to do the I/O for writing a page to its backing store.
Data Type	Unsigned integer
Default	<code>throttelfree / 2</code>
Range	The minimum value is 64 KB or 1/512th of physical memory, whichever is greater, expressed as pages using the page size returned by <code>getpagesize(3C)</code> . The maximum is the number of physical memory pages. The maximum value should be no more than 2 percent of physical memory. The system does not enforce this range, other than that described in the Validation section.
Units	Pages
Dynamic?	Yes, unless dynamic reconfiguration operations that add or delete memory occur. At that point, the value is reset to the value provided in <code>/etc/system.d/file</code> or calculated from the new physical memory value.
Validation	If <code>pageout_reserve</code> is greater than <code>throttelfree / 2</code> , <code>pageout_reserve</code> is set to <code>throttelfree / 2</code> . No message is displayed.
Implicit	The relationship of <code>lotsfree</code> being greater than <code>desfree</code> , which is greater than <code>minfree</code> , should be maintained at all times.
When to Change	The default value is generally adequate. For systems with relatively static workloads and large amounts of memory, lower this value. The

minimum acceptable value is 64 KB, expressed as pages using the page size returned by `getpagesize`.

Commitment Level Unstable

pages_before_pager Parameter

Description	Defines part of a system threshold that immediately frees pages after an I/O completes instead of storing the pages for possible reuse. The threshold is <code>lotsfree + pages_before_pager</code> . The NFS environment also uses this threshold to curtail its asynchronous activities as memory pressure mounts.
Data Type	Signed integer
Default	200
Range	1 to amount of physical memory
Units	Pages
Dynamic?	No
Validation	None
When to Change	<p>You might change this parameter when the majority of I/O is done for pages that are truly read or written once and never referenced again. Setting this variable to a larger amount of memory keeps adding pages to the free list.</p> <p>You might also change this parameter when the system is subject to bursts of severe memory pressure. A larger value here helps maintain a larger cushion against the pressure.</p>
Commitment Level	Unstable

pages_pp_maximum Parameter

Description	Defines the number of pages that must be unlocked. If a request to lock pages would force available memory below this value, that request is refused.
-------------	---

Data Type	Unsigned long
Default	The greater of (<code>tune_t_minarmem + 100</code> and [4% of memory available at boot time + 4 MB])
Range	Minimum value enforced by the system is <code>tune_t_minarmem + 100</code> . The system does not enforce a maximum value.
Units	Pages
Dynamic?	Yes, unless dynamic reconfiguration operations that add or delete memory occur. At that point, the value is reset to the value provided in <code>/etc/system.d/file</code> or was calculated from the new physical memory value.
Validation	<p>If the value specified in a file in the <code>/etc/system.d</code> directory or the calculated default is less than <code>tune_t_minarmem + 100</code>, the value is reset to <code>tune_t_minarmem + 100</code>.</p> <p>No message is displayed if the value from a <code>/etc/system.d/file</code> file is increased. Validation is done only at boot time and during dynamic reconfiguration operations that involve adding or deleting memory.</p>
When to Change	<p>When memory-locking requests fail or when attaching to a shared memory segment with the <code>SHARE_MMU</code> flag fails, yet the amount of memory available seems to be sufficient.</p> <p>Excessively large values can cause memory locking requests (<code>mlock</code>, <code>mlockall</code>, and <code>memcntl</code>) to fail unnecessarily. For more information, see the <code>mlock(3C)</code>, <code>mlockall(3C)</code>, and <code>memcntl(2)</code> man pages.</p>
Commitment Level	Unstable

slowscan Parameter

Description	Defines the minimum number of pages per second that the system looks at when attempting to reclaim memory.
Data Type	Signed integer
Default	The smaller of 1/20th of physical memory in pages and 100.
Range	1 to <code>fastscan / 2</code>

Units	Pages
Dynamic?	Yes, unless dynamic reconfiguration operations that add or delete memory occur. At that point, the value is reset to the value provided in <code>/etc/system.d/file</code> or calculated from the new physical memory value.
Validation	If <code>slowscan</code> is larger than <code>fastscan / 2</code> , <code>slowscan</code> is reset to <code>fastscan / 2</code> . No message is displayed.
When to Change	When more aggressive scanning of memory is preferred during periods of memory shortfall, especially when the system is subject to periods of intense memory demand.
Commitment Level	Unstable

throttlefree Parameter

Description	Specifies the memory level at which blocking memory allocation requests are put to sleep, even if the memory is sufficient to satisfy the request.
Data Type	Unsigned integer
Default	<code>minfree</code>
Range	<p>The minimum value is 128 KB or 1/256th of physical memory, whichever is greater, expressed as pages using the page size returned by <code>getpagesize</code>.</p> <p>The maximum value is the number of physical memory pages. The maximum value should be no more than 4 percent of physical memory. The system does not enforce this range other than that described in the Validation section.</p>
Units	Pages
Dynamic?	Yes, unless dynamic reconfiguration operations that add or delete memory occur. At that point, the value is reset to the value provided in <code>/etc/system.d/file</code> or calculated from the new physical memory value.
Validation	If <code>throttlefree</code> is greater than <code>desfree</code> , <code>throttlefree</code> is set to <code>minfree</code> . No message is displayed.

Implicit	The relationship of <code>lotsfree</code> is greater than <code>desfree</code> , which is greater than <code>minfree</code> , should be maintained at all times.
When to Change	The default value is generally adequate. For systems with relatively static workloads and large amounts of memory, lower this value. The minimum acceptable value is 128 KB, expressed as pages using the page size returned by <code>getpagesize</code> . For more information, see the getpagesize(3C) man page.
Commitment Level	Unstable

`tune_t_minarmem` Parameter

Description	Defines the minimum available resident (not swappable) memory to maintain necessary to avoid deadlock. Used to reserve a portion of memory for use by the core of the OS. Pages restricted in this way are not seen when the OS determines the maximum amount of memory available.
Data Type	Signed integer
Default	25
Range	1 to physical memory
Units	Pages
Dynamic?	No
Validation	None. Large values result in wasted physical memory.
When to Change	The default value is generally adequate. Consider increasing the default value if the system locks up and debugging information indicates that no memory was available.
Commitment Level	Unstable

Kernel Memory Allocator

The Oracle Solaris kernel memory allocator distributes chunks of memory for use by clients inside the kernel. The allocator creates a number of caches of varying size for use by its clients.

Clients can also request the allocator to create a cache for use by that client (for example, to allocate structures of a particular size). Statistics about each cache that the allocator manages can be seen by using the `kstat -c kmem_cache` command.

Occasionally, systems might panic because of memory corruption. The kernel memory allocator supports a debugging interface (a set of flags), that performs various integrity checks on the buffers. The kernel memory allocator also collects information on the allocators. The integrity checks provide the opportunity to detect errors closer to where they actually occurred. The collected information provides additional data for support people when they try to ascertain the reason for the panic.

Use of the flags incurs additional overhead and memory usage during system operations. The flags should only be used when a memory corruption problem is suspected.

kmem_flags Flag

Description The Oracle Solaris kernel memory allocator has various debugging and test options.

Five supported flag settings are described here.

Flag	Setting	Description
AUDIT	0x1	The allocator maintains a log that contains recent history of its activity. The number of items logged depends on whether CONTENTS is also set. The log is a fixed size. When space is exhausted, earlier records are reclaimed.
TEST	0x2	The allocator writes a pattern into freed memory and checks that the pattern is unchanged when the buffer is next allocated. If some portion of the buffer is changed, then the memory was probably used by a client that had previously allocated and freed the buffer. If an overwrite is identified, the system panics.
REDZONE	0x4	The allocator provides extra memory at the end of the requested buffer and inserts a special pattern into that memory. When the buffer is freed, the pattern is checked to see if data was written past the end of the buffer. If an overwrite is identified, the kernel panics.
CONTENTS	0x8	The allocator logs up to 256 bytes of buffer contents when the buffer is freed. This flag requires that AUDIT also be set.

The numeric value of these flags can be logically added together and set by a file in the `/etc/system.d` directory.

Flag	Setting	Description
LITE	0x100	Does minimal integrity checking when a buffer is allocated and freed. When enabled, the allocator checks that the redzone has not been written into, that a freed buffer is not being freed again, and that the buffer being freed is the size that was allocated. Do not combine this flag with any other flags.

Data Type	Signed integer
Default	0 (disabled)
Range	0 (disabled) or 1 - 15 or 256 (0x100)
Dynamic?	Yes. Changes made during runtime only affect new kernel memory caches. After system initialization, the creation of new caches is rare.
Validation	None
When to Change	When memory corruption is suspected
Commitment Level	Unstable

kmem_stackinfo Variable

Description	<p>If the <code>kmem_stackinfo</code> variable is enabled in an <code>/etc/system.d/file</code> at kernel thread creation time, the kernel thread stack is filled with a specific pattern instead of filled with zeros. During kernel thread execution, this kernel thread stack pattern is progressively overwritten. A simple count from the stack top until the pattern is not found gives a high watermark value, which is the maximum kernel stack space used by a kernel thread. This mechanism allows the following features:</p> <ul style="list-style-type: none"> ■ Compute the percentage of kernel thread stack really used (a high watermark) for current kernel threads in the system ■ When a kernel thread ends, the system logs the last kernel threads that have used the most of their kernel thread stacks before dying to a small circular memory buffer
Data Type	Unsigned integer
Default	0 (disabled)
Range	0 (disabled) or 1 (enabled)

Dynamic?	Yes
Validation	None
When to Change	When you want to monitor kernel thread stack usage. Keep in mind that when <code>kmem_stackinfo</code> is enabled, the performance of creating and deleting <code>kthreads</code> is decreased. For more information, see <i>Oracle Solaris Modular Debugger Guide</i> .
Zone Configuration	This parameter must be set in the global zone.
Commitment Level	Unstable

General Driver Parameters

This section describes other drivers that apply to the kernel.

SPARC: `dax_stats_flags` Flag

Description	This parameter controls what <code>dax</code> <code>kstats</code> are collected by the <code>dax</code> driver. This parameter can be set through the <code>/etc/system.d</code> directory. See “/etc/system.d/ Directory Files” on page 18 for more information. Alternatively, you can also use the <code>mdb --kernel -w --unsafe-write-access</code> command. To read the parameter's current value, use the <code>mdb --kernel --unsafe-io-access dax_stats_flags/D</code> . For information about the <code>mdb --kernel -w --unsafe-write-access</code> and <code>mdb --kernel --unsafe-io-access</code> commands, see “kmdb Debugger Entry” in Oracle Solaris Modular Debugger Guide and the <code>mdb(1)</code> man page. Note that you should use the <code>--kernel</code> option instead of the obsolescent <code>-k</code> option.
Data Type	Unsigned Integer
Default	1
Range	Possible Values <ul style="list-style-type: none"> ▪ 1 – <code>dax</code> unit statistics collection only, excluding queue and CPU statistics.

	<ul style="list-style-type: none"> ▪ 2 – dax queue and dax CPU statistics collection. This setting is not recommended because collecting queue and CPU statistics can have an impact on performance. ▪ 3 – dax unit, queue and CPU statistics collection
Dynamic?	No
Validation	None
When to Change	When dax queue and or dax cpu statistics are needed.
Commitment Level	Unstable

ddi_msix_alloc_limit Parameter

Description	x86 only: This parameter controls the number of Extended Message Signaled Interrupts (MSI-X) that a device instance can allocate. Due to an existing system limitation, the default value is 2. You can increase the number of MSI-X interrupts that a device instance can allocate by increasing the value of this parameter. This parameter can be set either by editing an <code>/etc/system.d/file</code> or by setting it with <code>mdb</code> before the device driver attach occurs.
Data Type	Signed integer
Default	SPARC based systems: 8 x86 based systems: 2 If the system supports x2APIC, the <code>apix</code> module can increase the default value to 8.
Range	2-8
Dynamic?	Yes
Validation	None
When to Change	To increase the number of MSI-X interrupts that a device instance can allocate. However, if you increase the number of MSI-X interrupts that a device instance can allocate, adequate interrupts might not be available to satisfy all allocation requests. If this happens, some devices might stop functioning or the system might fail to boot. Reduce the value or remove the parameter in this case.

Commitment Level Unstable

moddebug Parameter

Description	When this parameter is enabled, messages about various steps in the module loading process are displayed.
Data Type	Signed integer
Default	0 (messages off)
Range	Here are the most useful values: <ul style="list-style-type: none">■ 0x80000000 – Prints [un] loading... message. For every module loaded, messages such as the following appear on the console and in the /var/adm/messages file:<pre>Apr 20 17:18:04 neo genunix: [ID 943528 kern.notice] load 'sched/TS_DPTBL' id 15 loaded @ 0x7be1b2f8/0x19c8380 size 176/2096 Apr 20 17:18:04 neo genunix: [ID 131579 kern.notice] installing TS_DPTBL, module id 15.</pre>■ 0x40000000 – Prints detailed error messages. For every module loaded, messages such as the following appear on the console and in the /var/adm/messages file:<pre>Apr 20 18:30:00 neo unix: Errno = 2 Apr 20 18:30:00 neo unix: kobj_open: vn_open of /platform/sun4v/ kernel/exec/sparcv9/intpexec fails Apr 20 18:30:00 neo unix: Errno = 2 Apr 20 18:30:00 neo unix: kobj_open: '/kernel/exec/sparcv9/ intpexec' Apr 20 18:30:00 neo unix: vp = 60015777600 Apr 20 18:30:00 neo unix: kobj_close: 0x60015777600 Apr 20 18:30:00 neo unix: kobj_open: vn_open of /platform/ SUNW,Sun-Fire-T200/kernel/exec/sparcv9 /intpexec fails, Apr 20 18:30:00 neo unix: Errno = 2 Apr 20 18:30:00 neo unix: kobj_open: vn_open of /platform/sun4v/ kernel/exec/sparcv9/intpexec fails</pre>■ 0x20000000 - Prints even more detailed messages. This value doesn't print any additional information beyond what the 0x40000000 flag

does during system boot. However, this value does print additional information about releasing the module when the module is unloaded.

These values can be added together to set the final value.

Dynamic?	Yes
Validation	None
When to Change	When a module is either not loading as expected, or the system seems to hang while loading modules. Note that when <code>0x40000000</code> is set, system boot is slowed down considerably by the number of messages written to the console.
Commitment Level	Unstable

Network Driver Parameters

This section describes network parameters that affect the kernel.

IP Protocol Parameters in the Kernel

The following IP parameters can be set only in a file in the `/etc/system.d` directory. After the file is modified, reboot the system.

For example, the following entry sets the `ipcl_conn_hash_size` parameter:

```
set ip:ipcl_conn_hash_size=value
```

`ip_squeue_worker_wait` Parameter

Description	Governs the maximum delay in waking up a worker thread to process TCP/IP packets that are enqueued on an squeue. An <i>squeue</i> is a serialization queue that is used by the TCP/IP kernel code to process TCP/IP packets.
Default	10 milliseconds
Range	0 – 50 milliseconds

Dynamic?	Yes
When to Change	<p>Consider tuning this parameter if latency is an issue, and network traffic is light. For example, if the stem serves mostly interactive network traffic.</p> <p>The default value usually works best on a network file server, a web server, or any stem that has substantial network traffic.</p>
Zone Configuration	This parameter can only be set in the global zone.
Commitment Level	Unstable

ip_queue_fanout Parameter

Description	<p>Determines the mode of associating TCP/IP connections with queues.</p> <p>A value of 0 associates a new TCP/IP connection with the CPU that creates the connection. A value of 1 associates the connection with multiple queues that belong to different CPUs.</p>
Default	1
Range	0 or 1
Dynamic?	Yes
When to Change	<p>Consider setting this parameter to 1 to spread the load across all CPUs in certain situations. For example, when the number of CPUs exceed the number of NICs, and one CPU is not capable of handling the network load of a single NIC, change this parameter to 1.</p>
Zone Configuration	This parameter can only be set in the global zone.
Commitment Level	Unstable

ipcl_conn_hash_size Parameter

Description	<p>Controls the size of the connection hash table used by IP. The default value of 0 means that the system automatically sizes an appropriate value for this parameter at boot time, depending on the available memory.</p>
-------------	---

Data Type	Unsigned integer
Default	0
Range	0 to 82,500
Dynamic?	No. The parameter can only be changed at boot time.
When to Change	If the system consistently has tens of thousands of TCP connections, the value can be increased accordingly. Increasing the hash table size means that more memory is wired down, thereby reducing available memory to user applications.
Commitment Level	Unstable

igb Parameters

intr_force Parameter

Description	This parameter is used to force an interrupt type, such as MSI, MSI-X, or legacy, that is used by the <code>igb</code> network driver. This parameter can be set by editing the <code>/etc/driver/drv/igb.conf</code> file before the <code>igb</code> driver attach occurs.
Data Type	Unsigned integer
Default	0 (do not force an interrupt type)
Range	0 (do not force an interrupt type) 1 (force MSI-X interrupt type) 2 (force MSI interrupt type) 3 (force legacy interrupt type)
Dynamic?	No
Validation	None
When to Change	To force an interrupt type that is used by the <code>igb</code> network driver.
Commitment Level	Unstable

mr_enable Parameter

Description	This parameter enables or disables multiple receive and transmit queues that are used by the <code>igb</code> network driver. This parameter can be set by editing the <code>/etc/driver/drv/igb.conf</code> file before the <code>igb</code> driver attach occurs.
Data Type	Boolean
Default	0 (disable multiple queues)
Range	0 (disable multiple queues) or 1 (enable multiple queues)
Dynamic?	No
Validation	None
When to Change	To enable or disable multiple receive and transmit queues that are used by the <code>igb</code> network driver.
Commitment Level	Unstable

ixgbe Parameters

intr_throttling Parameter

Description	This parameter controls the interrupt throttling rate of the <code>ixgbe</code> network driver. You can increase the rate of interrupt by decreasing the value of this parameter. This parameter can be set by editing the <code>/etc/driver/drv/ixgbe.conf</code> file before the <code>ixgbe</code> driver attach occurs.
Data Type	Unsigned integer
Default	200
Range	0 to 65535
Dynamic?	No
Validation	None

When to Change	To change the interrupt throttling rate that is used by the <code>ixgbe</code> network driver.
Commitment Level	Unstable

rx_copy_threshold Parameter

Description	This parameter controls the receive buffer copy threshold that is used by the <code>ixgbe</code> network driver. You can increase the receive buffer copy threshold by increasing the value of this parameter. This parameter can be set by editing the <code>/etc/driver/drv/ixgbe.conf</code> file before the <code>ixgbe</code> driver attach occurs.
Data Type	Unsigned integer
Default	128
Range	0 to 9126
Dynamic?	No
Validation	None
When to Change	To change the receive buffer copy threshold that is used by the <code>ixgbe</code> network driver.
Commitment Level	Unstable

rx_limit_per_intr Parameter

Description	This parameter controls the maximum number of receive queue buffer descriptors per interrupt that are used by the <code>ixgbe</code> network driver. You can increase the number of receive queue buffer descriptors by increasing the value of this parameter. This parameter can be set by editing the <code>/etc/driver/drv/ixgbe.conf</code> file before the <code>ixgbe</code> driver attach occurs.
Data Type	Unsigned integer
Default	256
Range	16 to 4096

Dynamic?	No
Validation	None
When to Change	To change the number of receive queue buffer descriptors that are handled per interrupt by the <code>ixgbe</code> network driver.
Commitment Level	Unstable

rx_queue_number Parameter

Description	This parameter controls the number of receive queues that are used by the <code>ixgbe</code> network driver. You can increase the number of receive queues by increasing the value of this parameter. This parameter can be set by editing the <code>/etc/driver/drv/ixgbe.conf</code> file before the <code>ixgbe</code> driver attach occurs.
Data Type	Unsigned integer
Default	8
Range	1 to 64
Dynamic?	No
Validation	None
When to Change	To change the number of receive queues that are used by the <code>ixgbe</code> network driver.
Commitment Level	Unstable

rx_ring_size Parameter

Description	This parameter controls the receive queue size that is used by the <code>ixgbe</code> network driver. You can increase the receive queue size by increasing the value of this parameter. This parameter can be set by editing the <code>/etc/driver/drv/ixgbe.conf</code> file before the <code>ixgbe</code> driver attach occurs.
Data Type	Unsigned integer
Default	1024

Range	64 to 4096
Dynamic?	No
Validation	None
When to Change	To change the receive queue size that is used by the <code>ixgbe</code> network driver.
Commitment Level	Unstable

tx_copy_threshold Parameter

Description	This parameter controls the transmit buffer copy threshold that is used by the <code>ixgbe</code> network driver. You can increase the transmit buffer copy threshold by increasing the value of this parameter. This parameter can be set by editing the <code>/etc/driver/drv/ixgbe.conf</code> file before the <code>ixgbe</code> driver attach occurs.
Data Type	Unsigned integer
Default	512
Range	0 to 9126
Dynamic?	No
Validation	None
When to Change	To change the transmit buffer copy threshold that is used by the <code>ixgbe</code> network driver.
Commitment Level	Unstable

tx_queue_number Parameter

Description	This parameter controls the number of transmit queues that are used by the <code>ixgbe</code> network driver. You can increase the number of transmit queues by increasing the value of this parameter. This parameter can be set by editing the <code>/etc/driver/drv/ixgbe.conf</code> file before the <code>ixgbe</code> driver attach occurs.
-------------	---

Data Type	Unsigned integer
Default	8
Range	1 to 32
Dynamic?	No
Validation	None
When to Change	To change the number of transmit queues that are used by the <code>ixgbe</code> network driver.
Commitment Level	Unstable

tx_ring_size Parameter

Description	This parameter controls the transmit queue size that is used by the <code>ixgbe</code> network driver. You can increase the transmit queue size by increasing the value of this parameter. This parameter can be set by editing the <code>/etc/driver/drv/ixgbe.conf</code> file before the <code>ixgbe</code> driver attach occurs.
Data Type	Unsigned integer
Default	1024
Range	64 to 4096
Dynamic?	No
Validation	None
When to Change	To change the transmit queue size that is used by the <code>ixgbe</code> network driver.
Commitment Level	Unstable

General I/O Parameters

This section describes parameters in function of input and output processes in the kernel.

maxphys Parameter

Description	Defines the maximum size of physical I/O requests. If a driver encounters a request larger than this size, the driver breaks the request into maxphys sized chunks. File systems can and do impose their own limit.
Data Type	Signed integer
Default	131,072 (sun4v) or 57,344 (x86). The sd driver uses the value of 1,048,576 if the drive supports wide transfers. The ssd driver uses 1,048,576 by default.
Range	stem-specific page size to MAXINT
Units	Bytes
Dynamic?	Yes, but many file systems load this value into a per-mount point data structure when the file system is mounted. A number of drivers load the value at the time a device is attached to a driver-specific data structure.
Validation	None
When to Change	When doing I/O to and from raw devices in large chunks. Note that a DBMS doing OLTP operations issues large numbers of small I/Os. Changing maxphys does not result in any performance improvement in that case.
Commitment Level	Unstable

rlim_fd_cur Parameter

Description	Defines the "soft" limit on file descriptors that a single process can have open. A process might adjust its file descriptor limit to any value up to the "hard" limit defined by rlim_fd_max by using the setrlimit() call or by issuing the limit command in whatever shell it is running. You do not require superuser privilege to adjust the limit to any value less than or equal to the hard limit.
Data Type	Signed integer

Default	256 through Oracle Solaris 11.4 SRU 26 4095 starting with Oracle Solaris 11.4 SRU 27
Range	128 to MAXINT
Units	File descriptors
Dynamic?	No
Validation	Compared to <code>rlim_fd_max</code> . If <code>rlim_fd_cur</code> is greater than <code>rlim_fd_max</code> , <code>rlim_fd_cur</code> is reset to <code>rlim_fd_max</code> .
When to Change	When the default number of open files for a process is not enough. Increasing this value means only that it might not be necessary for a program to use <code>setrlimit</code> to increase the maximum number of file descriptors available to it.
Commitment Level	Unstable

`rlim_fd_max` Parameter

Description	Specifies the "hard" limit on file descriptors that a single process might have open. Overriding this limit requires superuser privilege.
Data Type	Signed integer
Default	65536 through Oracle Solaris 11.4 SRU 26 65535 starting with Oracle Solaris 11.4 SRU 27
Range	128 to MAXINT
Units	File descriptors
Dynamic?	No
Validation	Compared to <code>rlim_fd_sys</code> . If <code>rlim_fd_max</code> is greater than <code>rlim_fd_sys</code> , <code>rlim_fd_max</code> is reset to <code>rlim_fd_sys</code> .
When to Change	When the maximum number of open files for a process is not enough. Other limitations in system facilities can mean that a larger number of file descriptors is not as useful as it might be. For example:

`select` is by default limited to 1024 descriptors per `fd_set` in 32-bit applications. For more information, see the [select\(3C\)](#) man page. A 32-bit application code can be recompiled with a larger `fd_set` size (less than or equal to 65,536). A 64-bit application uses an `fd_set` size of 65,536, which cannot be changed.

An alternative to changing this on a system wide basis is to use the `plimit` command. If a parent process has its limits changed by `plimit`, all children inherit the increased limit. This alternative is useful for daemons such as `inetd`.

Commitment Level Unstable

`rlim_fd_sys` Parameter

Description	Specifies the maximum limit to which a process can raise its hard limit on file descriptors. This parameter specifies the system maximum value for the <code>process.max-file-descriptor</code> resource control. You cannot override this limit. You can only change this limit if your system runs at least Oracle Solaris 11.4 SRU 27.
Data Type	Unsigned integer
Default	MAXINT through Oracle Solaris 11.4 SRU 26 Starting with Oracle Solaris 11.4 SRU 27, calculated based on <code>physmem</code> to be approximately 65K per gigabyte of memory. The value is rounded up to the nearest value of $(2^N)-1$.
Range	128 to MAXINT
Dynamic?	No
Validation	Compared to <code>rlim_fd_max</code> . If <code>rlim_fd_sys</code> is less than <code>rlim_fd_max</code> , <code>rlim_fd_sys</code> is reset to <code>rlim_fd_max</code>
When to Change	When the maximum hard limit of open files for a process is insufficient or when a system restricts the maximum hard limit for privileged processes
Commitment Level	Unstable

General File System Parameters

This section describes parameters that relate to file systems.

dnlc_dir_enable Parameter

Description Enables large directory caching

Note - This parameter has no effect on NFS or ZFS file systems.

Data Type Unsigned integer

Default 1 (enabled)

Range 0 (disabled) or 1 (enabled)

Dynamic? Yes, but do not change this tunable dynamically. You can enable this parameter if it was originally disabled. Or, you can disable this parameter if it was originally enabled. However, enabling, disabling, and then enabling this parameter might lead to stale directory caches.

Validation No

When to Change Directory caching has no known problems. However, if problems occur, then set `dnlc_dir_enable` to 0 to disable caching.

Commitment Level Unstable

dnlc_dir_max_size Parameter

Description Specifies the maximum number of entries cached for one directory.

Note - This parameter has no effect on NFS or ZFS file systems.

Data Type Unsigned integer

Default MAXUINT (no maximum)

Range 0 to MAXUINT

Dynamic?	Yes, this parameter can be changed at any time.
Validation	None
When to Change	If performance problems occur with large directories, then decrease <code>dnlc_dir_max_size</code> .
Commitment Level	Unstable

`dnlc_dir_min_size` Parameter

Description	Specifies the minimum number of entries cached for one directory.
-------------	---

Note - This parameter has no effect on NFS or ZFS file systems.

Data Type	Unsigned integer
Default	40
Range	0 to MAXUINT (no maximum)
Units	Entries
Dynamic?	Yes, this parameter can be changed at any time.
Validation	None
When to Change	If performance problems occur with caching small directories, then increase <code>dnlc_dir_min_size</code> . Note that individual file systems might have their own range limits for caching directories.
Commitment Level	Unstable

`dnlc_dircache_percent` Parameter

Description	Calculates the maximum percentage of physical memory that the DNLC directory cache can consume.
Data Type	Integer

Default	100
Range	0 to 100
Units	Percentage
Dynamic?	No
Validation	At boot time, the value range is checked and default value is enforced.
When to Change	When the system experiences a memory shortage and high kernel memory consumption, consider lowering this value. If performance issues are seen with the default value, consider increasing the value.

Note - The DNLC is used by UFS and ZFS file systems and NFS clients. Setting this tunable might be considered for better performance when there are memory shortages and high kernel memory consumption or when a memory is needed by the ARC or other kernel caches.

Commitment Level Unstable

ncsize Parameter

Description	<p>Defines the number of entries in the directory name look-up cache (DNLC). This parameter is used by UFS, NFS, and ZFS to cache elements of path names that have been resolved.</p> <p>The DNLC also caches negative look-up information, which means it caches a name not found in the cache.</p>
Data Type	Signed integer
Default	$(4 \times (v.v_proc + \text{maxusers}) + 320) + (4 \times (v.v_proc + \text{maxusers}) + 320) / 100$
Range	0 to MAXINT
Units	DNLC entries
Dynamic?	No
Validation	None. Larger values cause the time it takes to unmount a file system to increase as the cache must be flushed of entries for that file system during the unmount process.

When to Change	<p>You can use the <code>kstat -n dnlcstats</code> command to view the number of hits and misses in the DNLC. A high ratio of misses to hits might indicate that the DNLC is too small. Increasing the value of <code>ncsize</code> can help improve performance.</p> <p>Excessive values of <code>ncsize</code> have an immediate impact on the system memory usage. Memory that is used directly by the DNLC increases in proportion to <code>ncsize</code>. In addition, caching more entries in the DNLC might require filesystem context relating to those entries to remain in memory when it would otherwise be freed.</p>
Commitment Level	Unstable

TMPFS Parameters

This section describes parameters that affect temporary file storage facility.

tmpfs:tmpfs_maxkmem Parameter

Description	Defines the maximum amount of kernel memory that TMPFS can use for its data structures (tmpnodes and directory entries).
Data Type	Unsigned long
Default	One page or 4 percent of physical memory, whichever is greater.
Range	Number of bytes in one page (8192 for sun4v systems, 4096 for all other systems) to 25 percent of the available kernel memory at the time TMPFS was first used.
Units	Bytes
Dynamic?	Yes
Validation	None
When to Change	<p>Increase if the following message is displayed on the console or written in the messages file:</p> <pre>tmp_memalloc: tmpfs over memory limit</pre>

The current amount of memory used by TMPFS for its data structures is held in the `tmp_kmemspace` field. This field can be examined with a kernel debugger.

Commitment Level Unstable

tmpfs:tmpfs_minfree Parameter

Description Defines the minimum amount of swap space that TMPFS leaves for the rest of the system.

Data Type Signed long

Default 256

Range 0 to maximum swap space size

Units Pages

Dynamic? Yes

Validation None

When to Change To maintain a reasonable amount of swap space on systems with large amounts of TMPFS usage, you can increase this number. The limit has been reached when the console or messages file displays the following message:

fs-name: File system full, swap space limit exceeded

Commitment Level Unstable

Pseudo Terminals

Pseudo terminals (ptys) are used for two purposes in Oracle Solaris software:

- Supporting remote logins
- Providing the interface through which the X Window system creates command interpreter windows

The default number of pseudo terminals is sufficient for a desktop workstation. So, tuning focuses on the number of ptys available for remote logins.

The default number of ptys is now based on the amount of memory on the system. This default should be changed only to restrict or increase the number of users who can log in to the system.

Three related variables are used in the configuration process:

- `pt_cnt` – Default maximum number of ptys.
- `pt_pctofmem` – Percentage of kernel memory that can be dedicated to pseudo terminal support structures. A value of zero means that no remote users can log in to the system.
- `pt_max_pty` – Hard maximum for number of ptys.

`pt_cnt` has a default value of zero, which tells the system to limit logins based on the amount of memory specified in `pt_pctofmem`, unless `pt_max_pty` is set. If `pt_cnt` is non-zero, ptys are allocated until this limit is reached. When that threshold is crossed, the system looks at `pt_max_pty`. If `pt_max_pty` has a non-zero value, it is compared to `pt_cnt`. The pseudo terminal allocation is allowed if `pt_cnt` is less than `pt_max_pty`. If `pt_max_pty` is zero, `pt_cnt` is compared to the number of ptys supported based on `pt_pctofmem`. If `pt_cnt` is less than this value, the pseudo terminal allocation is allowed. Note that the limit based on `pt_pctofmem` only comes into play if both `pt_cnt` and `ptms_ptymax` have default values of zero.

To put a hard limit on ptys that is different than the maximum derived from `pt_pctofmem`, set `pt_cnt` and `ptms_ptymax` in `/etc/system.d/file` to the preferred number of ptys. The setting of `ptms_pctofmem` is not relevant in this case.

To dedicate a different percentage of system memory to pseudo terminal support and let the operating system manage the explicit limits, do the following:

- Do not set `pt_cnt` or `ptms_ptymax` in `/etc/system.d/file`.
- Set `pt_pctofmem` in `/etc/system.d/file` to the preferred percentage. For example, set `pt_pctofmem=10` for a 10 percent setting.

Note that the memory is not actually allocated until it is used in support of a pseudo terminal. Once memory is allocated, it remains allocated.

pt_cnt Parameter

Description	The number of available <code>/dev/pts</code> entries is dynamic up to a limit determined by the amount of physical memory available on the system. <code>pt_cnt</code> is one of three variables that determines the minimum number of logins that the system can accommodate. The default maximum number
-------------	--

of `/dev/pts` devices the system can support is determined at boot time by computing the number of pseudo terminal structures that can fit in a percentage of system memory (see `pt_pctofmem`). If `pt_cnt` is zero, the system allocates up to that maximum. If `pt_cnt` is non-zero, the system allocates to the greater of `pt_cnt` and the default maximum.

Data Type	Unsigned integer
Default	0
Range	0 to <code>maxpid</code>
Units	Logins/windows
Dynamic?	No
Validation	None
When to Change	When you want to explicitly control the number of users who can remotely log in to the system.
Commitment Level	Unstable

pt_max_pty Parameter

Description	Defines the maximum number of ptys the system offers
Data Type	Unsigned integer
Default	0 (Uses system-defined maximum)
Range	0 to <code>MAXUINT</code>
Units	Logins/windows
Dynamic?	Yes
Validation	None
Implicit	Should be greater than or equal to <code>pt_cnt</code> . Value is not checked until the number of ptys allocated exceeds the value of <code>pt_cnt</code> .

When to Change	When you want to place an absolute ceiling on the number of logins supported, even if the system could handle more based on its current configuration values.
Commitment Level	Unstable

pt_pctofmem Parameter

Description	Specifies the maximum percentage of physical memory that can be consumed by data structures to support <code>/dev/pts</code> entries. A system consumes 176 bytes per <code>/dev/pts</code> entry.
Data Type	Unsigned integer
Default	5
Range	0 to 100
Units	Percentage
Dynamic?	No
Validation	None
When to Change	When you want to either restrict or increase the number of users who can log in to the system. A value of zero means that no remote users can log in to the system.
Commitment Level	Unstable

STREAMS Parameters

This section describes STREAMS-related parameters.

nstrpush Parameter

Description	Specifies the number of modules that can be inserted into (pushed onto) a STREAM.
-------------	---

Data Type	Signed integer
Default	9
Range	9 to 16
Units	Modules
Dynamic?	Yes
Validation	None
When to Change	At the direction of your software vendor. No messages are displayed when a STREAM exceeds its permitted push count. A value of EINVAL is returned to the program that attempted the push.
Commitment Level	Unstable

strmsgsz Parameter

Description	Specifies the maximum number of bytes that a single system call can pass to a STREAM to be placed in the data part of a message. Any write exceeding this size is broken into multiple messages. For more information, see the write(2) man page.
Data Type	Signed integer
Default	65,536
Range	0 to 262,144
Units	Bytes
Dynamic?	Yes
Validation	None
When to Change	When putmsg calls return ERANGE. For more information, see the putmsg(2) man page.
Commitment Level	Unstable

strctlSz Parameter

Description	Specifies the maximum number of bytes that a single system call can pass to a STREAM to be placed in the control part of a message
Data Type	Signed integer
Default	1024
Range	0 to MAXINT
Units	Bytes
Dynamic?	Yes
Validation	None
When to Change	At the direction of your software vendor. putmsg () calls return ERANGE if they attempt to exceed this limit.
Commitment Level	Unstable

System V Message Queues

System V message queues provide a message-passing interface that enables the exchange of messages by queues created in the kernel. Interfaces are provided in the Oracle Solaris environment to enqueue and dequeue messages. Messages can have a type associated with them. Enqueueing places messages at the end of a queue. Dequeueing removes the first message of a specific type from the queue or the first message if no type is specified.

For detailed information about tuning these system resources, see [Chapter 6, “About Resource Controls”](#) in *Administering Resource Management in Oracle Solaris 11.4*.

System V Semaphores

System V semaphores provide counting semaphores in the Oracle Solaris OS. A *semaphore* is a counter used to provide access to a shared data object for multiple processes. In addition to the standard set and release operations for semaphores, System V semaphores can have values

that are incremented and decremented as needed (for example, to represent the number of resources available). System V semaphores also provide the ability to do operations on a group of semaphores simultaneously as well as to have the system undo the last operation by a process if the process dies.

Timer Behavior

This section describes parameters that determine timer behavior.

hires_tick Parameter

Description	When set, this parameter causes the Oracle Solaris OS to use a system clock rate of 1000 instead of the default value of 100.
Data Type	Signed integer
Default	0
Range	0 (disabled) or 1 (enabled)
Dynamic?	No. Causes new system timing variable to be set at boot time. Not referenced after boot.
Validation	None
When to Change	When you want timeouts with a resolution of less than 10 milliseconds, and greater than or equal to 1 millisecond.
Commitment Level	Unstable

timer_max Parameter

Description	Specifies the number of POSIX™ timers available.
Data Type	Signed integer
Default	1000

Range	0 to MAXINT
Dynamic?	No. Increasing the value can cause a system crash.
Validation	None
When to Change	When the default number of timers offered by the system is inadequate. Applications receive an EAGAIN error when executing <code>timer_create</code> system calls.
Commitment Level	Unstable

SPARC: Platform Specific Parameters

The following parameters apply to sun4v platforms.

default_tsb_size Parameter

Description	Selects size of the initial translation storage buffers (TSBs) allocated to all processes.
Data Type	Integer
Default	Default is 0 (8 KB), which corresponds to 512 entries
Range	Possible values are:

Value	Description
0	8 KB
1	16 KB
3	32 KB
4	128 KB
5	256 KB
6	512 KB
7	1 MB

Dynamic?	Yes
----------	-----

Validation	None
When to Change	Generally, you do not need to change this value. However, doing so might provide some advantages if the majority of processes on the system have a larger than average working set, or if resident set size (RSS) sizing is disabled.
Commitment Level	Unstable

enable_tsb_rss_sizing Parameter

Description	Enables a resident set size (RSS) based TSB sizing heuristic.
Data Type	Boolean
Default	1 (TSBs can be resized)
Range	0 (TSBs remain at <code>tsb_default_size</code>) or 1 (TSBs can be resized) If set to 0, then <code>tsb_rss_factor</code> is ignored.
Dynamic?	Yes
Validation	Yes
When to Change	Can be set to 0 to prevent growth of the TSBs. Under most circumstances, this parameter should be left at the default setting.
Commitment Level	Unstable

tsb_alloc_hiwater_factor Parameter

Description	Initializes <code>tsb_alloc_hiwater</code> to impose an upper limit on the amount of physical memory that can be allocated for translation storage buffers (TSBs) as follows: $\text{tsb_alloc_hiwater} = \text{physical memory (bytes)} / \text{tsb_alloc_hiwater_factor}$ When the memory that is allocated to TSBs is equal to the value of <code>tsb_alloc_hiwater</code> , the TSB memory allocation algorithm attempts to reclaim TSB memory as pages are unmapped.
-------------	--

Exercise caution when using this factor to increase the value of `tsb_alloc_hiwater`. To prevent system hangs, the resulting high water value must be considerably lower than the value of `swarfs_minfree` and `segspt_minfree`.

Data Type	Integer
Default	32
Range	1 to MAXINIT Note that a factor of 1 makes all physical memory available for allocation to TSBs, which could cause the system to hang. A factor that is too high will not leave memory available for allocation to TSBs, decreasing system performance.
Dynamic?	Yes
Validation	None
When to Change	Change the value of this parameter if the system has many processes that attach to very large shared memory segments. Under most circumstances, tuning of this variable is not necessary.
Commitment Level	Unstable

tsb_rss_factor Parameter

Description	Controls the RSS to TSB span ratio of the RSS sizing heuristic. This factor divided by 512 yields the percentage of the TSB span which must be resident in memory before the TSB is considered as a candidate for resizing.
Data Type	Integer
Default	384, resulting in a value of 75%. Thus, when the TSB is 3/4 full, its size will be increased. Note that some virtual addresses typically map to the same slot in the TSB. Therefore, conflicts can occur before the TSB is at 100% full.
Range	0 to 512
Dynamic?	Yes

Validation	None
When to Change	<p>If the system is experiencing an excessive number of traps due to TSB misses, for example, due to virtual address conflicts in the TSB, you might consider decreasing this value toward 0.</p> <p>For example, changing <code>tsb_rss_factor</code> to 256 (effectively, 50%) instead of 384 (effectively, 75%) might help eliminate virtual address conflicts in the TSB in some cases, but will use more kernel memory, particularly on a heavily loaded system.</p> <p>TSB activity can be monitored with the <code>trapstat -T</code> command.</p>
Commitment Level	Unstable

Locality Group Parameters

This section provides generic memory tunables, which apply to any SPARC or x86 system that uses a Non-Uniform Memory Architecture (NUMA).

`lgrp_mem_pset_aware` Parameter

Description	<p>If a process is running within a user processor set, this variable determines whether <i>randomly</i> placed memory for the process is selected from among all the lgroups in the system or only from those lgroups that are spanned by the processors in the processor set.</p> <p>For more information about creating processor sets, see the psrset(8) man page.</p>
Data Type	Boolean
Default	0, the Oracle Solaris OS selects memory from all the lgroups in the system
Range	<ul style="list-style-type: none"> ■ 0, the Oracle Solaris OS selects memory from all the lgroups in the system (default) ■ 1, try selecting memory only from those lgroups that are spanned by the processors in the processor set. If the first attempt fails, memory can be allocated in any lgroup.
Dynamic?	No

Validation	None
When to Change	Setting this value to a value of one (1) might lead to more reproducible performance when processor sets are used to isolate applications from one another.
Commitment Level	Uncommitted

lpg_alloc_prefer Parameter

Description	<p>Controls a heuristic for allocation of large memory pages when the requested page size is not immediately available in the local memory group, but could be satisfied from a remote memory group.</p> <p>By default, the Oracle Solaris OS allocates a remote large page if local free memory is fragmented, but remote free memory is not. Setting this parameter to 1 indicates that additional effort should be spent attempting to allocate larger memory pages locally, potentially moving smaller pages around to coalesce larger pages in the local memory group.</p>
Data Type	Boolean
Default	0 (Prefer remote allocation if local free memory is fragmented and remote free memory is not)
Range	<p>0 (Prefer remote allocation if local free memory is fragmented and remote free memory is not)</p> <p>1 (Prefer local allocation whenever possible, even if local free memory is fragmented and remote free memory is not)</p>
Dynamic?	No
Validation	None
When to Change	<p>This parameter might be set to 1 if long-running programs on the system tend to allocate memory that is accessed by a single program, or if memory that is accessed by a group of programs is known to be running in the same locality group (lgroup). In these circumstances, the extra cost of page coalesce operations can be amortized over the long run of the programs.</p> <p>This parameter might be left at the default value (0) if multiple programs tend to share memory across different locality groups, or if pages tend to</p>

be used for short periods of time. In these circumstances, quick allocation of the requested size tends to be more important than allocation in a particular location.

TLB miss activity might be observed by using the `trapstat -T` command.

Commitment Level	Uncommitted
------------------	-------------

Oracle Solaris ZFS Tunable Parameters

This chapter describes ZFS tunable parameters that might need consideration, depending on your system and application requirements. In addition, tunable recommendations for using ZFS with database products are provided.

- [“Tuning ZFS Considerations”](#)
- [“ZFS Memory Management Parameters”](#)
- [“ZFS File-Level Prefetch”](#)
- [“ZFS Device I/O Queue Depth”](#)
- [“Tuning ZFS When Using Flash Storage”](#)
- [“Tuning ZFS for Database Products”](#)

For other types of tunable parameters, refer to the following:

- Oracle Solaris kernel tunable parameters – [Chapter 2, “Oracle Solaris Kernel Tunable Parameters”](#)
- NFS tunable parameters – [Chapter 4, “NFS Tunable Parameters”](#)
- Internet Protocol Suite tunable parameters – [Chapter 5, “Internet Protocol Suite Tunable Parameters”](#)
- System facility tunable parameters – [Chapter 6, “System Facility Parameters”](#)

Tuning ZFS Considerations

Review the following considerations before tuning ZFS:

- Default values are generally the best value. If a better value exists, it should be the default. While alternative values might help a given workload, it could quite possibly degrade some other aspects of performance. Occasionally, catastrophically so.
- The ZFS best practices should be followed before ZFS tuning is applied. These practices are a set of recommendations that have been shown to work in different environments and

are expected to keep working in the foreseeable future. So, before turning to tuning, make sure you've read and understood the best practices. For more information, see [Chapter 12, “Recommended Oracle Solaris ZFS Practices”](#) in *Managing ZFS File Systems in Oracle Solaris 11.4*.

- Unless noted otherwise, the tunable parameters are global and impact ZFS behavior across the system.

ZFS Memory Management Parameters

This section describes parameters related to ZFS memory management.

user_reserve_hint_pct ZFS Parameter

Description Informs the system about how much memory is reserved for application use, and therefore limits how much memory can be used by the ZFS ARC cache as the cache increases over time.

By means of this parameter, administrators can maintain a large reserve of available free memory for future application demands. The `user_reserve_hint_pct` parameter is intended to be used in place of the [“zfs_arc_max Parameter”](#) parameter to restrict the growth of the ZFS ARC cache.

Note - Review Document 1663862.1, *Memory Management Between ZFS and Applications in Oracle Solaris 11.x*, in [My Oracle Support \(MOS\)](#) for guidance in tuning this parameter.

Data Type	Unsigned Integer (64-bit)
Default	0
	If a dedicated system is used to run a set of applications with a known memory footprint, set the parameter to the value of that footprint, such as the sum of the SGA of Oracle database.
	To assign a value to the parameter, run the script that is provided in Document 1663862.1 in My Oracle Support (MOS) . To make the tuning persistent across reboots, refer to script output for instructions about using <code>-p</code> option.
Range	0-99

Units	Percent
Dynamic	Yes You can adjust the setting of this parameter dynamically on a running system.
When to Change	For upward adjustments, increase the value if the initial value is determined to be insufficient over time for application requirements, or if application demand increases on the system. Perform this adjustment only within a scheduled system maintenance window. After you have changed the value, reboot the system. For downward adjustments, decrease the value if allowed by application requirements. Make sure to use decrease the value only by small amounts, no greater than 5% at a time.
Commitment Level	Unstable

zfs_arc_min Parameter

Description	Determines the minimum size of the ZFS Adaptive Replacement Cache (ARC). See also “ zfs_arc_max Parameter”.
Data Type	Unsigned Integer (64-bit)
Default	1% of total memory (physmem)
Range	Default value to <code>zfs_arc_max</code>
Units	Bytes
Dynamic?	No
Validation	Yes, the range is validated.
When to Change	When a system's workload demand for memory fluctuates, the ZFS ARC caches data at a period of weak demand and then shrinks at a period of strong demand. However, ZFS does not shrink below the value of <code>zfs_arc_min</code> . Generally, you do not need to change the default value.
Commitment Level	Unstable

zfs_arc_max Parameter

Description	Determines the maximum size of the ZFS Adaptive Replacement Cache (ARC). However, see “ user_reserve_hint_pct ZFS Parameter ”. See also “ zfs_arc_min Parameter ”
Data Type	Unsigned Integer (64-bit)
Default	75% of memory on systems with less than 4 GB of memory physmem minus 1 GB on systems with greater than 4 GB of memory
Range	Default value of <code>zfs_arc_min</code> to <code>physmem</code>
Units	Bytes
Dynamic?	No
Validation	Yes, the range is validated.
When to Change	If a future memory requirement is significantly large and well defined, you might consider reducing the value of this parameter to cap the ARC so that it does not compete with the memory requirement. For example, if you know that a future workload requires 20% of memory, it makes sense to cap the ARC such that it does not consume more than the remaining 80% of memory.
Commitment Level	Unstable

ZFS File-Level Prefetch

This section describes the parameter that regulates the behavior of the prefetching mechanism.

zfs_prefetch_disable Parameter

Description	This parameter determines a file-level prefetching mechanism called <code>zfetch</code> . This mechanism looks at the patterns of reads to files and
-------------	--

anticipates on some reads, thereby reducing application wait times. The current behavior suffers from two drawbacks:

- Sequential read patterns made of small reads very often hit in the cache. In this case, the current behavior consumes a significant amount of CPU time trying to find the next I/O to issue, whereas performance is governed more by the CPU availability.
- The `zfetch` code has been observed to limit scalability of some loads. CPU profiling can be done by using the `lockstat -I` command or `er_kernel`. For detailed descriptions, see the following sources:
 - `lockstat(8)`
 - Oracle Developer Studio documentation (<https://docs.oracle.com/en/operating-systems/studio.html>)
 - Oracle Developer Studio Documentation (<https://www.oracle.com/application-development/technologies/developerstudio-documentation.html>)

Although never recommended, you can disable prefetching by setting `zfs_prefetch_disable` in a file in the `/etc/system.d` directory. For instructions, see “[/etc/system.d/ Directory Files](#)” on page 18.

Device-level prefetching is disabled when `zfs_vdev_cache_size` is disabled. This means that tuning `vdev_cache_shift` is no longer necessary if `zfs_vdev_cache_size` is disabled.

Data Type	Boolean
Default	0 (enabled)
Range	0 (enabled) or 1 (disabled)
Dynamic?	Yes
Validation	No
When to Change	If the results of <code>er_kernel</code> show significant time in <code>zfetch_*</code> functions, or if lock profiling with <code>lockstat</code> shows contention around <code>zfetch</code> locks, and if the affected workload is critical, then disabling file level prefetching should be considered. Other workloads that are running concurrently can be degraded.
Commitment Level	Unstable

ZFS Device I/O Queue Depth

This section describes the parameter pertaining to concurrent I/O processes for ZFS.

zfs_vdev_max_pending Parameter

Description	This parameter controls the maximum number of concurrent I/Os pending to each device.
Data Type	Integer
Default	10
Range	0 to MAXINT
Dynamic?	Yes
Validation	No
When to Change	<p>In a storage array where LUNs are made of a large number of disk drives, the ZFS queue can become a limiting factor on read IOPS. This behavior is one of the underlying reasoning for the best practice of presenting as many LUNS as there are backing spindles to the ZFS storage pool. That is, if you create LUNS from a 10 disk-wide array level raid-group, then using 5 to 10 LUNs to build a storage pool allows ZFS to manage enough of an I/O queue without the need to set this specific tunable.</p> <p>However, when no separate intent log is in use and the pool is made of JBOD disks, using a small <code>zfs_vdev_max_pending</code> value, such as 10, can improve the synchronous write latency as those are competing for the disk resource. Using separate intent log devices can alleviate the need to tune this parameter for loads that are synchronously write intensive since those synchronous writes are not competing with a deep queue of non-synchronous writes.</p> <p>Tuning this parameter is not expected to be effective for NVRAM-based storage arrays in the case where volumes are made of small number of spindles. However, when ZFS is presented with a volume made of a large (greater than 10) number of spindles, then this parameter can limit the read throughput obtained on the volume. The reason is that with a maximum of 10 or 35 queued I/Os per LUN, this can translate into less</p>

than 1 I/O per storage spindle, which is not enough for individual disks to deliver their IOPS. This issue would appear in `iostat actv` queue output approaching the value of `zfs_vdev_max_pending`.

Device drivers may also limit the number of outstanding I/Os per LUN. If you are using LUNs on storage arrays that can handle large numbers of concurrent IOPS, then the device driver constraints can limit concurrency. Consult the configuration for the drivers your system uses. For example, the limit for the QLogic FCI HBA (qlc) driver is described as the `execution-throttle` parameter in `/kernel/drv/qlc.conf`.

Commitment Level Unstable

Tuning ZFS When Using Flash Storage

The following information applies to Flash SSDs, F20 PCIe Accelerator Card, F40 PCIe Accelerator Card, F5100 Flash Storage Array, and F80 PCIe Accelerator Card.

Review the following general comments when using ZFS with Flash storage:

- Consider using LUNs or low latency disks that are managed by a controller with persistent memory, if available, for the ZIL (ZFS intent log). This option can be considerably more cost effective than using flash for low latency commits. The size of the log devices must only be large enough to hold 10 seconds of maximum write throughput. Examples would include a storage array based LUN, or a disk connected to an HBA with a battery protected write cache.
If no such device is available, segment a separate pool of flash devices for use as log devices in a ZFS storage pool.
- The F40, F20, and F80 Flash Accelerator cards contain and export 4 independent flash modules to the OS. The F5100 contains up to 80 independent flash modules. Each flash module appear to the operating system as a single device. SSDs are viewed as a single device by the OS. Flash devices may be used as ZFS log devices to reduce commit latency, particularly if used in an NFS server. For example, a single flash module of a flash device used as a ZFS log device can reduce latency of single lightly threaded operations by 10x. More flash devices can be striped together to achieve higher throughput for large amounts of synchronous operations.
- Log devices should be mirrored for reliability. For maximum protection, the mirrors should be created on separate flash devices. In the case of F20, F40, and F80 PCIe accelerator cards, maximum protection is achieved by ensuring that mirrors reside on different physical PCIe cards. Maximum protection with the F5100 storage array is obtained by placing mirrors on separate F5100 devices.

- Flash devices that are not used as log devices may be used as second level cache devices. This serves to both offload IOPS from primary disk storage and also to improve read latency for commonly used data.

Adding Flash Devices as ZFS Log or Cache Devices

Review the following recommendations when adding flash devices as ZFS log or cache devices.

- A ZFS log or cache device can be added to an existing ZFS storage pool by using the `zpool add` command. Be very careful with `zpool add` commands. Mistakenly adding a log device as a normal pool device is a mistake that will require you to destroy and restore the pool from scratch. Individual log devices themselves can be removed from a pool.
- Familiarize yourself with the `zpool add` command before attempting this operation on active storage. You can use the `zpool add -n` option to preview the configuration without creating the configuration. For example, the following incorrect `zpool add` preview syntax attempts to add a device as a log device:

```
# zpool add -n tank c4t1d0
vdev verification failed: use -f to override the following errors:
mismatched replication level: pool uses mirror and new vdev is disk
Unable to build pool from specified devices: invalid vdev configuration
```

This is the correct `zpool add` preview syntax for adding a log device to an existing pool:

```
# zpool add -n tank log c4t1d0
would update 'tank' to the following configuration:
tank
mirror
c4t0d0
c5t0d0
logs
c4t1d0
```

If multiple devices are specified, they are striped together. For more information, see the examples below or the [zpool\(8\)](#) man page.

A flash device, `c4t1d0`, can be added as a ZFS log device:

```
# zpool add pool log c4t1d0
```

If 2 flash devices are available, you can add mirrored log devices:

```
# zpool add pool log mirror c4t1d0 c4t2d0
```

Available flash devices can be added as a cache device for reads.

```
# zpool add pool cache c4t3d0
```

You can't mirror cache devices, they will be striped together.

```
# zpool add pool cache c4t3d0 c4t4d0
```

Ensuring Proper Cache Flush Behavior for Flash and NVRAM Storage Devices

ZFS is designed to work with storage devices that manage a disk-level cache. ZFS commonly asks the storage device to ensure that data is safely placed on stable storage by requesting a cache flush. For JBOD storage, this works as designed and without problems. For many NVRAM-based storage arrays, a performance problem might occur if the array takes the cache flush request and actually does something with it, rather than ignoring it. Some storage arrays flush their large caches despite the fact that the NVRAM protection makes those caches as good as stable storage.

ZFS issues infrequent flushes (every 5 second or so) after the uberblock updates. The flushing infrequency is fairly inconsequential so no tuning is warranted here. ZFS also issues a flush every time an application requests a synchronous write (`O_DSYNC`, `fsync`, NFS commit, and so on). The completion of this type of flush is waited upon by the application and impacts performance. Greatly so, in fact. From a performance standpoint, this neutralizes the benefits of having an NVRAM-based storage.

Cache flush tuning was recently shown to help flash device performance when used as log devices. When all LUNs exposed to ZFS come from NVRAM-protected storage array and procedures ensure that no unprotected LUNs will be added in the future, ZFS can be tuned to not issue the flush requests by setting `zfs_nocacheflush`. If some LUNs exposed to ZFS are not protected by NVRAM, then this tuning can lead to data loss, application level corruption, or even pool corruption. In some NVRAM-protected storage arrays, the cache flush command is a no-op, so tuning in this situation makes no performance difference.

A recent OS change is that the flush request semantic has been qualified to instruct storage devices to ignore the requests if they have the proper protection. This change requires a fix to our disk drivers and for the NVRAM device to support the updated semantics. If the NVRAM device does not recognize this improvement, use these instructions to tell the Oracle Solaris OS not to send any synchronize cache commands to the array. If you use these instructions, make sure all targeted LUNs are indeed protected by NVRAM.

Occasionally, flash and NVRAM devices do not properly advertise to the OS that they are non-volatile devices, and that caches do not need to be flushed. Cache flushing is an expensive operation. Unnecessary flushes can drastically impede performance in some cases.

Review the following `zfs_nocacheflush` syntax restrictions before applying the tuning entries below:

- The tuning syntax below can be included in `sd.conf` but there must be only a single `sd-config-list` entry per vendor/product.
- If multiple devices entries are desired, multiple pairs of vendor IDs and `sd` tuning strings can be specified on the same line by using the following syntax:

```
#           "012345670123456789012345", "tuning   ",
sd-config-list="|-VID1-||-----PID1-----|", "param1:val1, param2:val2",
               "|-VIDN-||-----PIDN-----|", "param1:val1, param3:val3";
```

Make sure the vendor ID (VID) string is padded to 8 characters and the Product ID (PID) string is padded to 16 characters as described in the preceding example.



Caution - All cache sync commands are ignored by the device. Use at your own risk.

1. Use the `format` utility to run the `inquiry` subcommand on a LUN from the storage array. For example:

```
# format
.
.
.
Specify disk (enter its number): x
format> inquiry
Vendor:   ATA
Product:  Marvell
Revision: XXXX
format>
```

2. Select one of the following based on your architecture:
 - For all devices, copy the file `/kernel/drv/sd.conf` to the `/etc/driver/drv/sd.conf` file.
 - For F40 flash devices, add the following entry to `/kernel/drv/sd.conf`. In the entry below, ensure that `ATA` is padded to 8 characters, and `3E128-TS2-550B01` contains 16 characters. Total string length is 24.

```
sd-config-list="ATA      3E128-TS2-550B01", "disksort:false, cache-nonvolatile:
true, physical-block-size:4096";
```

- For F80 flash devices, add the following entry to `/kernel/drv/sd.conf`. Ensure that ATA is padded to 8 characters, and 3E128-TS2-550B01 contains 16 characters. Total string length is 24.

```
sd-config-list="ATA    2E256-TU2-510B00", "disksort:false, cache-nonvolatile:
true, physical-block-size:4096";
```

- For F20 and F5100 flash devices, choose one of the following based on your architecture. In the entries below, ATA is padded to 8 characters, and MARVELL SD88SA02 contains 16 characters. The total string length is 24.
- Add the following entry to `/etc/driver/drv/sd.conf`

```
sd-config-list="ATA    MARVELL SD88SA02", "throttle-max:32, disksort:false,
cache-nonvolatile:true";
```

3. Carefully add whitespace to make the vendor ID (VID) 8 characters long (here "ATA ") and Product ID (PID) 16 characters long (here MARVELL) in the `sd-config-list` entry as illustrated.
4. Reboot the system.

You can tune `zfs_nocacheflush` back to its default value (0) with no adverse effect on performance.

5. Confirm that the flush behavior is correct.

Use the script provided in [Appendix A, “System Check Script”](#) for verification.

Tuning ZFS for Database Products

Review the following considerations when using ZFS with a database product.

- If the database uses a fixed disk block or record size for I/O, set the `ZFS recordsize` property to match it. You can do this on a per-file system basis, even though multiple file systems might share a single pool.
- With ZFS's copy-on-write design, tuning down the `recordsize` is a way to improve OLTP performance at the expense of batch reporting queries.
- ZFS checksums every block stored on disk. This alleviates the need for the database layer to checksum data an additional time. If checksums are computed by ZFS instead of at the database layer, any discrepancy can be caught and fixed before the data is returned to the application.
- Keep pool space under 90% utilization to maintain pool performance.

For a comprehensive information about best practices when using ZFS Storage in an Exadata environment, log in to your My Oracle Support account (<https://support.oracle.com>) and refer to the following documents:

- Doc ID 2087231.1
- Doc ID 1354980.1

To tune ZFS for an Oracle Database, see [Configuring Oracle Solaris ZFS for an Oracle Database \(https://www.oracle.com/technetwork/server-storage/solaris/config-solaris-zfs-wp-167894.pdf\)](https://www.oracle.com/technetwork/server-storage/solaris/config-solaris-zfs-wp-167894.pdf).

Review the following considerations when using ZFS with MySQL.

- **ZFS recordsize**

Match the ZFS `recordsize` property to the storage engine block size for better OLTP performance.

- **InnoDB**

With a known application memory footprint, such as for a database application, you might cap the ARC size so that the application will not need to reclaim its necessary memory from the ZFS cache.

- Create a separate pool for the logs.
- Set a different path for data and log in the `my.cnf` file.
- Set the ZFS `recordsize` property to 16K for the InnoDB data files, and use the default `recordsize` value for InnoDB logs, prior to creating data files.

NFS Tunable Parameters

This section describes the NFS tunable parameters.

- [“Tuning the NFS Environment” on page 97](#)
- [“NFS Module Parameters” on page 98](#)
- [“NFS-Related SMF Configuration Parameters” on page 127](#)
- [“rpcmod Module Parameters” on page 129](#)

For other types of tunable parameters, refer to the following:

- Oracle Solaris kernel tunable parameters – [Chapter 2, “Oracle Solaris Kernel Tunable Parameters”](#)
- Oracle Solaris ZFS tunable parameters – [Chapter 3, “Oracle Solaris ZFS Tunable Parameters”](#)
- Internet Protocol Suite tunable parameters – [Chapter 5, “Internet Protocol Suite Tunable Parameters”](#)
- System facility tunable parameters – [Chapter 6, “System Facility Parameters”](#)

Tuning the NFS Environment

You can define NFS parameters in files in the `/etc/system.d` directory, which are read during the boot process. Each parameter includes the name of its associated kernel module. For more information, see [“Tuning an Oracle Solaris System” on page 17](#).



Caution - The names of the parameters, the modules that they reside in, and the default values can change between releases. Check the documentation for the version of the active SunOS release before making changes or applying values from previous releases.

NFS Module Parameters

This section describes parameters related to the NFS kernel module.

nfs:nfs_allow_preepoch_time Parameter

Description	<p>Controls whether files with incorrect or <i>negative</i> time stamps should be made visible on the NFS client.</p> <p>Historically, neither the NFS client nor the NFS server would do any range checking on the file times being returned. The over-the-wire timestamp values are unsigned and 32-bits long. So, all values have been legal.</p> <p>The timestamp values on the 64-bit Oracle Solaris kernel are signed and 64-bits long. It is impossible to determine whether a time field represents a full 32-bit time or a negative time, that is, a time prior to January 1, 1970.</p> <p>It is impossible to determine whether to sign extend a time value when converting from 32 bits to 64 bits. The time value should be sign extended if the time value is truly a negative number. However, the time value should not be sign extended if it does truly represent a full 32-bit time value. This problem is resolved by simply disallowing full 32-bit time values.</p>
Data Type	Integer (32-bit)
Default	0 (32-bit time stamps disabled)
Range	0 (32-bit time stamps disabled) or 1 (32-bit time stamps enabled)
Units	Boolean values
Dynamic?	Yes
Validation	None
When to Change	Even during normal operation, it is possible for the timestamp values on some files to be set very far in the future or very far in the past. If access to these files is preferred using NFS mounted file systems, set this parameter to 1 to allow the timestamp values to be passed through unchecked.

Commitment Level Unstable

nfs:nfs_async_clusters Parameter

Description	<p>Controls the mix of asynchronous requests that are generated by the NFS version 2 client. The four types of asynchronous requests are read-ahead, putpage, pageio, and readdir-ahead. The client attempts to round-robin between these different request types to attempt to be fair and not starve one request type in favor of another.</p> <p>However, the functionality in some NFS version 2 servers such as write gathering depends upon certain behaviors of existing NFS Version 2 clients. In particular, this functionality depends upon the client sending out multiple WRITE requests at about the same time. If one request is taken out of the queue at a time, the client would be defeating this server functionality designed to enhance performance for the client.</p> <p>Thus, use this parameter to control the number of requests of each request type that are sent out before changing types.</p>
Data Type	Unsigned integer (32-bit)
Default	1
Range	0 to $2^{32} - 1$
Units	Asynchronous requests
Dynamic?	Yes, but the cluster setting for a file system is set when the file system is mounted. To affect a particular file system, unmount and mount the file system after changing this parameter.
Validation	None. However, setting the value of this parameter to 0 causes all of the queued requests of a particular request type to be processed before moving on to the next type. This effectively disables the fairness portion of the algorithm.
When to Change	To increase the number of each type of asynchronous request that is generated before switching to the next type. Doing so might help with NFS server functionality that depends upon clusters of requests coming from the NFS client.
Commitment Level	Unstable

nfs:nfs3_async_clusters Parameter

Description	<p>Controls the mix of asynchronous requests that are generated by the NFS version 3 client. The five types of asynchronous requests are read-ahead, putpage, pageio, readdir-ahead, and commit. The client attempts to round-robin between these different request types to attempt to be fair and not starve one request type in favor of another.</p> <p>However, the functionality in some NFS version 3 servers such as write gathering depends upon certain behaviors of existing NFS version 3 clients. In particular, this functionality depends upon the client sending out multiple WRITE requests at about the same time. If one request is taken out of the queue at a time, the client would be defeating this server functionality designed to enhance performance for the client.</p> <p>Thus, use this parameter to control the number of requests of each request type that are sent out before changing types.</p>
Data Type	Unsigned integer (32-bit)
Default	1
Range	0 to $2^{32} - 1$
Units	Asynchronous requests
Dynamic?	Yes, but the cluster setting for a file system is set when the file system is mounted. To affect a particular file system, unmount and mount the file system after changing this parameter.
Validation	None. However, setting the value of this parameter to 0 causes all of the queued requests of a particular request type to be processed before moving on to the next type. This value effectively disables the fairness portion of the algorithm.
When to Change	To increase the number of each type of asynchronous operation that is generated before switching to the next type. Doing so might help with NFS server functionality that depends upon clusters of operations coming from the NFS client.
Commitment Level	Unstable

nfs:nfs4_async_clusters Parameter

Description	<p>Controls the mix of asynchronous requests that are generated by the NFS version 4 client. The six types of asynchronous requests are read-ahead, putpage, pageio, readdir-ahead, commit, and inactive. The client attempts to round-robin between these different request types to attempt to be fair and not starve one request type in favor of another.</p> <p>However, the functionality in some NFS version 4 servers such as write gathering depends upon certain behaviors of existing NFS version 4 clients. In particular, this functionality depends upon the client sending out multiple WRITE requests at about the same time. If one request is taken out of the queue at a time, the client would be defeating this server functionality designed to enhance performance for the client.</p> <p>Thus, use this parameter to control the number of requests of each request type that are sent out before changing types.</p>
Data Type	Unsigned integer (32-bit)
Default	1
Range	0 to $2^{32} - 1$
Units	Asynchronous requests
Dynamic?	Yes, but the cluster setting for a file system is set when the file system is mounted. To affect a particular file system, unmount and mount the file system after changing this parameter.
Validation	None. However, setting the value of this parameter to 0 causes all of the queued requests of a particular request type to be processed before moving on to the next type. This effectively disables the fairness portion of the algorithm.
When to Change	To increase the number of each type of asynchronous request that is generated before switching to the next type. Doing so might help with NFS server functionality that depends upon clusters of requests coming from the NFS client.
Commitment Level	Unstable

nfs:nfs_async_timeout Parameter

Description	Controls the duration of time that threads, which execute asynchronous I/O requests, sleep with nothing to do before exiting. When there are no more requests to execute, each thread goes to sleep. If no new requests come in before this timer expires, the thread wakes up and exits. If a request does arrive, a thread is woken up to execute requests until there are none again. Then, the thread goes back to sleep waiting for another request to arrive, or for the timer to expire.
Data Type	Integer (32-bit)
Default	6000 (1 minute expressed as 60 sec * 100Hz)
Range	0 to $2^{31} - 1$
Units	Hz. (Typically, the clock runs at 100Hz.)
Dynamic?	Yes
Validation	None. However, setting this parameter to a non positive value causes these threads exit as soon as there are no requests in the queue for them to process.
When to Change	If the behavior of applications in the system is known precisely and the rate of asynchronous I/O requests can be predicted, it might be possible to tune this parameter to optimize performance slightly in either of the following ways: <ul style="list-style-type: none">■ By making the threads expire more quickly, thus freeing up kernel resources more quickly■ By making the threads expire more slowly, thus avoiding thread create and destroy overhead
Commitment Level	Unstable

nfs:nfs3_bsize Parameter

Description	Controls the logical block size used by the NFS version 3 client. This block size represents the amount of data that the client attempts to read from or write to the NFS server when it needs to do an I/O.
-------------	--

Data Type	Unsigned integer (32-bit)
Default	32,768 (32 KB)
Range	0 to $2^{32} - 1$
Units	Bytes
Dynamic?	Yes, but the block size for a file system is set when the file system is mounted. To affect a particular file system, unmount and mount the file system after changing this parameter.
Validation	None. Setting this parameter too low or too high might cause the system to malfunction. Do not set this parameter to anything less than PAGESIZE for the specific platform. Do not set this parameter too high because it might cause the system to hang while waiting for memory allocations to be granted.
When to Change	Examine the value of this parameter when attempting to change the maximum data transfer size. Change this parameter in conjunction with <code>nfs:nfs3_max_transfer_size</code> parameter. If larger transfers are preferred, increase both parameters. If smaller transfers are preferred, then just reducing this parameter should suffice.
Commitment Level	Unstable

nfs:nfs4_bsize Parameter

Description	Controls the logical block size used by the NFS version 4 client. This block size represents the amount of data that the client attempts to read from or write to the NFS server when it needs to do an I/O.
Data Type	Unsigned integer (32-bit)
Default	32,768 (32 KB)
Range	0 to $2^{32} - 1$
Units	Bytes
Dynamic?	Yes, but the block size for a file system is set when the file system is mounted. To affect a particular file system, unmount and mount the file system after changing this parameter.

Validation	None. Setting this parameter too low or too high might cause the system to malfunction. Do not set this parameter to anything less than <code>PAGESIZE</code> for the specific platform. Do not set this parameter too high because it might cause the system to hang while waiting for memory allocations to be granted.
When to Change	Examine the value of this parameter when attempting to change the maximum data transfer size. Change this parameter in conjunction with <code>nfs:nfs4_max_transfer_size</code> parameter. If larger transfers are preferred, increase both parameters. If smaller transfers are preferred, then just reducing this parameter should suffice.
Commitment Level	Unstable

nfs:nfs_cots_timeo Parameter

Description	Controls the default RPC timeout for NFS version 2 mounted file systems using connection-oriented transports such as TCP for the transport protocol.
Data Type	Unsigned integer (32-bit)
Default	600 (60 seconds)
Range	0 to $2^{32} - 1$
Units	10th of seconds
Dynamic?	Yes, but the RPC timeout for a file system is set when the file system is mounted. To affect a particular file system, unmount and mount the file system after changing this parameter.
Validation	None
When to Change	<p>TCP does a good job ensuring requests and responses are delivered appropriately. However, if the round-trip times are very large in a particularly slow network, the NFS version 2 client might time out prematurely.</p> <p>Increase this parameter to prevent the client from timing out incorrectly. The range of values is very large, so increasing this value too much might result in situations where a retransmission is not detected for long periods of time.</p>

Commitment Level Unstable

nfs:nfs3_cots_timeo Parameter

Description	Controls the default RPC timeout for NFS version 3 mounted file systems using connection-oriented transports such as TCP for the transport protocol.
Data Type	Unsigned integer (32-bit)
Default	600 (60 seconds)
Range	0 to $2^{32} - 1$
Units	10th of seconds
Dynamic?	Yes, but the RPC timeout for a file system is set when the file system is mounted. To affect a particular file system, unmount and mount the file system after changing this parameter.
Validation	None
When to Change	<p>TCP does a good job ensuring requests and responses are delivered appropriately. However, if the round-trip times are very large in a particularly slow network, the NFS version 3 client might time out prematurely.</p> <p>Increase this parameter to prevent the client from timing out incorrectly. The range of values is very large, so increasing this value too much might result in situations where a retransmission is not detected for long periods of time.</p>
Commitment Level	Unstable

nfs:nfs4_cots_timeo Parameter

Description	<p>Controls the default RPC timeout for NFS version 4 mounted file systems using connection-oriented transports such as TCP for the transport protocol.</p> <p>The NFS Version 4 protocol specification disallows retransmission over the same TCP connection. Thus, this parameter primarily controls how</p>
-------------	--

quickly the NFS client responds to certain events, such as detecting a forced unmount operation or detecting how quickly the NFS server fails over to a new server.

Data Type	Unsigned integer (32-bit)
Default	600 (60 seconds)
Range	0 to $2^{32} - 1$
Units	10th of seconds
Dynamic?	Yes, but this parameter is set when the file system is mounted. To affect a particular file system, unmount and mount the file system after changing this parameter.
Validation	None
When to Change	<p>TCP does a good job ensuring requests and responses are delivered appropriately. However, if the round-trip times are very large in a particularly slow network, the NFS version 4 client might time out prematurely.</p> <p>Increase this parameter to prevent the client from timing out incorrectly. The range of values is very large, so increasing this value too much might result in situations where a retransmission is not detected for long periods of time.</p>
Commitment Level	Unstable

nfs:nfs_disable_rddir_cache Parameter

Description	Controls the use of a cache to hold responses from REaddir and REaddirplus requests. This cache avoids over-the-wire calls to the NFS server to retrieve directory information.
Data Type	Integer (32-bit)
Default	0 (caching enabled)
Range	0 (caching enabled) or 1 (caching disabled)
Units	Boolean values

Dynamic?	Yes
Validation	None
When to Change	<p>Examine the value of this parameter if interoperability problems develop due to a NFS server that does not update the modification time on a directory when a file or directory is created in it or removed from it. The symptoms are that new names do not appear in directory listings after they have been added to the directory or that old names do not disappear after they have been removed from the directory.</p> <p>This parameter controls the caching for NFS version 2, 3, and 4 mounted file systems. This parameter applies to all NFS mounted file systems, so caching cannot be disabled or enabled on a per file system basis.</p> <p>If you disable this parameter, you should also disable the following parameters to prevent bad entries in the DNLC negative cache:</p> <ul style="list-style-type: none"> ▪ “nfs:nfs_lookup_neg_cache Parameter” on page 111 ▪ “nfs:nfs3_lookup_neg_cache Parameter” on page 112 ▪ “nfs:nfs4_lookup_neg_cache Parameter” on page 113
Commitment Level	Unstable

nfs:nfs_do_symlink_cache Parameter

Description	Controls whether the contents of symbolic link files are cached for NFS version 2 mounted file systems.
Data Type	Integer (32-bit)
Default	1 (caching enabled)
Range	0 (caching disabled) or 1 (caching enabled)
Units	Boolean values
Dynamic?	Yes
Validation	None
When to Change	If a NFS server changes the contents of a symbolic link file without updating the modification timestamp on the file or if the granularity of

the timestamp is too large, then changes to the contents of the symbolic link file might not be visible on the NFS client for extended periods. In this case, use this parameter to disable the caching of symbolic link contents. Doing so makes the changes immediately visible to applications running on the client.

Commitment Level Unstable

nfs:nfs3_do_symlink_cache Parameter

Description Controls whether the contents of symbolic link files are cached for NFS version 3 mounted file systems.

Data Type Integer (32-bit)

Default 1 (caching enabled)

Range 0 (caching disabled) or 1 (caching enabled)

Units Boolean values

Dynamic? Yes

Validation None

When to Change If a NFS server changes the contents of a symbolic link file without updating the modification timestamp on the file or if the granularity of the timestamp is too large, then changes to the contents of the symbolic link file might not be visible on the NFS client for extended periods. In this case, use this parameter to disable the caching of symbolic link contents. Doing so makes the changes immediately visible to applications running on the client.

Commitment Level Unstable

nfs:nfs4_do_symlink_cache Parameter

Description Controls whether the contents of symbolic link files are cached for NFS version 4 mounted file systems.

Data Type	Integer (32-bit)
Default	1 (caching enabled)
Range	0 (caching disabled) or 1 (caching enabled)
Units	Boolean values
Dynamic?	Yes
Validation	None
When to Change	If a NFS server changes the contents of a symbolic link file without updating the modification timestamp on the file or if the granularity of the timestamp is too large, then changes to the contents of the symbolic link file might not be visible on the NFS client for extended periods. In this case, use this parameter to disable the caching of symbolic link contents. Doing so makes the changes immediately visible to applications running on the client.
Commitment Level	Unstable

nfs:nfs_dynamic Parameter

Description	Controls whether a feature known as <i>dynamic retransmission</i> is enabled for NFS version 2 mounted file systems using connectionless transports such as UDP. This feature attempts to reduce retransmissions by monitoring NFS server response times and then adjusting RPC timeouts and read- and write- transfer sizes.
Data Type	Integer (32-bit)
Default	1 (enabled)
Range	0 (disabled) or 1 (enabled)
Dynamic?	Yes, but this parameter is set per file system at mount time. To affect a particular file system, unmount and mount the file system after changing this parameter.
Validation	None

When to Change	Do not change this parameter.
Commitment Level	Unstable

nfs:nfs3_dynamic Parameter

Description	Controls whether a feature known as <i>dynamic retransmission</i> is enabled for NFS version 3 mounted file systems using connectionless transports such as UDP. This feature attempts to reduce retransmissions by monitoring NFS server response times and then adjusting RPC timeouts and read- and write- transfer sizes.
Data Type	Integer (32-bit)
Default	0 (disabled)
Range	0 (disabled) or 1 (enabled)
Units	Boolean values
Dynamic?	Yes, but this parameter is set per file system at mount time. To affect a particular file system, unmount and mount the file system after changing this parameter.
Validation	None
When to Change	Do not change this parameter.
Commitment Level	Unstable

nfs:nfs3_jukebox_delay Parameter

Description	Controls the duration of time that the NFS version 3 client waits to transmit a new request after receiving the NFS3ERR_JUKEBOX error from a previous request. The NFS3ERR_JUKEBOX error is generally returned from the NFS server when the file is temporarily unavailable for some reason. This error is generally associated with hierarchical storage, and CD or tape jukeboxes.
Data Type	Long integer (64-bit)

Default	1000 (10 seconds expressed as 10 sec * 100Hz)
Range	0 to $2^{63} - 1$ on 64-bit platforms
Units	Hz. (Typically, the clock runs at 100Hz.)
Dynamic?	Yes
Validation	None
When to Change	Examine the value of this parameter and perhaps adjust it to match the behaviors exhibited by the NFS server. Increase this value if the delays in making the file available are long in order to reduce network overhead due to repeated retransmissions. Decrease this value to reduce the delay in discovering that the file has become available.
Commitment Level	Unstable

nfs:nfs_lookup_neg_cache Parameter

Description	Controls whether a negative name cache is used for NFS version 2 mounted file systems. This negative name cache records file names that were looked up, but not found. The cache is used to avoid over-the-network look-up requests made for file names that are already known to not exist.
Data Type	Integer (32-bit)
Default	1 (enabled)
Range	0 (disabled) or 1 (enabled)
Units	Boolean values
Dynamic?	Yes
Validation	None
When to Change	For the cache to perform correctly, negative entries must be strictly verified before they are used. This consistency mechanism is relaxed slightly for read-only mounted file systems. It is assumed that the file

system on the NFS server is not changing or is changing very slowly, and that it is okay for such changes to propagate slowly to the NFS client. The consistency mechanism becomes the normal attribute cache mechanism in this case.

If file systems are mounted read-only on the NFS client, but are expected to change on the NFS server and these changes need to be seen immediately by the client, use this parameter to disable the negative cache.

If you disable the `nfs:nfs_disable_rmdir_cache` parameter, you should probably also disable this parameter. For more information, see [“nfs:nfs_disable_rmdir_cache Parameter” on page 106](#).

Commitment Level Unstable

nfs:nfs3_lookup_neg_cache Parameter

Description	Controls whether a negative name cache is used for NFS version 3 read-only mounted file systems. This negative name cache records file names that were looked up, but were not found. The cache is used to avoid over-the-network look-up requests made for file names that are already known to not exist.
Data Type	Integer (32-bit)
Default	1 (enabled)
Range	0 (disabled) or 1 (enabled)
Units	Boolean values
Dynamic?	Yes
Validation	None
When to Change	For the cache to perform correctly, negative entries must be strictly verified before they are used. This consistency mechanism is relaxed slightly for read-only mounted file systems. It is assumed that the file system on the NFS server is not changing or is changing very slowly, and that it is okay for such changes to propagate slowly to the NFS client. The consistency mechanism becomes the normal attribute cache mechanism in this case.

If file systems are mounted read-only on the client, but are expected to change on the NFS server and these changes need to be seen immediately by the NFS client, use this parameter to disable the negative cache.

If you disable the “[nfs:nfs_disable_rddir_cache Parameter](#)” on page 106 parameter, you should probably also disable this parameter.

Commitment Level Unstable

nfs:nfs4_lookup_neg_cache Parameter

Description	Controls whether a negative name cache is used for NFS version 4 mounted file systems. This negative name cache records file names that were looked up, but were not found. The cache is used to avoid over-the-network look-up requests made for file names that are already known to not exist.
Data Type	Integer (32-bit)
Default	1 (enabled)
Range	0 (disabled) or 1 (enabled)
Units	Boolean values
Dynamic?	Yes
Validation	None
When to Change	<p>For the cache to perform correctly, negative entries must be strictly verified before they are used. This consistency mechanism is relaxed slightly for read-only mounted file systems. It is assumed that the file system on the NFS server is not changing or is changing very slowly, and that it is okay for such changes to propagate slowly to the NFS client. The consistency mechanism becomes the normal attribute cache mechanism in this case.</p> <p>If file systems are mounted read-only on the NFS client, but are expected to change on the NFS server and these changes need to be seen immediately by the client, use this parameter to disable the negative cache.</p>

If you disable the “[nfs:nfs_disable_rddir_cache Parameter](#)” on page 106 parameter, you should probably also disable this parameter.

Commitment Level Unstable

nfs:nfs_max_threads Parameter

Description Controls the number of kernel threads that perform asynchronous I/O for each file system for the NFS version 2 client. Because NFS is based on RPC and RPC is inherently synchronous, separate execution contexts are required to perform NFS operations that are asynchronous from the calling thread.

The operations that can be executed asynchronously are read for read-ahead, readdir for readdir read-ahead, write for putpage and pageio operations, commit, and inactive for cleanup operations that the NFS client performs when it stops using a file.

Data Type Unsigned short

Default 8

Range 0 to $2^{16} - 1$

Units Threads

Dynamic? Yes, but this parameter is set per file system at mount time. To affect a particular file system, unmount and mount the file system after changing this parameter.

Validation None

When to Change To increase or reduce the number of simultaneous I/O operations that are outstanding at any given time. For example, for a very low bandwidth network, you might want to decrease this value so that the NFS client does not overload the network. Alternately, if the network is very high bandwidth, and the NFS client and NFS server have sufficient resources, you might want to increase this value. Doing so can more effectively utilize the available network bandwidth, and the client and server resources.

Commitment Level Unstable

nfs:nfs3_max_threads Parameter

Description	<p>Controls the number of kernel threads that perform asynchronous I/O for each file system for the NFS version 3 client. Because NFS is based on RPC and RPC is inherently synchronous, separate execution contexts are required to perform NFS operations that are asynchronous from the calling thread.</p> <p>The operations that can be executed asynchronously are read for read-ahead, readdir for readdir read-ahead, write for putpage and pageio requests, and commit.</p>
Data Type	Unsigned short
Default	8
Range	0 to $2^{16} - 1$
Units	Threads
Dynamic?	Yes, but this parameter is set per file system at mount time. To affect a particular file system, unmount and mount the file system after changing this parameter.
Validation	None
When to Change	To increase or reduce the number of simultaneous I/O operations that are outstanding at any given time. For example, for a very low bandwidth network, you might want to decrease this value so that the NFS client does not overload the network. Alternately, if the network is very high bandwidth, and the NFS client and NFS server have sufficient resources, you might want to increase this value. Doing so can more effectively utilize the available network bandwidth, and the client and server resources.
Commitment Level	Unstable

nfs:nfs4_max_threads Parameter

Description	<p>Controls the number of kernel threads that perform asynchronous I/O for each file system for the NFS version 4 client. Because NFS is based on RPC and RPC is inherently synchronous, separate execution contexts</p>
-------------	--

are required to perform NFS operations that are asynchronous from the calling thread.

The operations that can be executed asynchronously are read for read-ahead, write-behind, directory read-ahead, and cleanup operations that the client performs when it stops using a file.

Data Type	Unsigned short
Default	8
Range	0 to $2^{16} - 1$
Units	Threads
Dynamic?	Yes, but this parameter is set per file system at mount time. To affect a particular file system, unmount and mount the file system after changing this parameter.
Validation	None
When to Change	To increase or reduce the number of simultaneous I/O operations that are outstanding at any given time. For example, for a very low bandwidth network, you might want to decrease this value so that the NFS client does not overload the network. Alternately, if the network is very high bandwidth, and the NFS client and NFS server have sufficient resources, you might want to increase this value. Doing so can more effectively utilize the available network bandwidth, and the client and server resources.
Commitment Level	Unstable

nfs:nfs3_max_transfer_size Parameter

Description	Controls the maximum size of the data portion of an NFS version 3 READ, WRITE, REaddir, or REaddirplus request. This parameter controls both the maximum size of the request that the NFS server returns as well as the maximum size of the request that the NFS client generates.
Data Type	Unsigned integer (32-bit)
Default	4,194,304 (4 MB)

Range	0 to $2^{31} - 1$
Units	Bytes
Dynamic?	Yes, but this parameter is set per file system at mount time. To affect a particular file system, unmount and mount the file system after changing this parameter.
Validation	<p>None. However, setting the maximum transfer size on the NFS server to 0 is likely to cause NFS clients to malfunction or just decide not to attempt to talk to the server.</p> <p>There is also a limit on the maximum transfer size when using NFS over the UDP transport. UDP has a hard limit of 64 KB per datagram. This 64 KB must include the RPC header as well as other NFS information, in addition to the data portion of the request. Setting the limit too high might result in errors from UDP and communication problems between the NFS client and the NFS server.</p>
When to Change	<p>To tune the size of data transmitted over the network. In general, the “nfs:nfs3_bsize Parameter” on page 102 parameter should also be updated to reflect changes in this parameter.</p> <p>For example, when you attempt to increase the transfer size beyond 32 KB, update <code>nfs:nfs3_bsize</code> to reflect the increased value. Otherwise, no change in the over-the-wire request size is observed.</p> <p>If you want to use a smaller transfer size than the default transfer size, use the mount command's <code>-wsize -rsize</code> option on a per-file system basis.</p>
Commitment Level	Unstable

nfs:nfs4_max_transfer_size Parameter

Description	Controls the maximum size of the data portion of an NFS version 4 READ, WRITE, REaddir, or REaddirplus request. This parameter controls both the maximum size of the request that the NFS server returns as well as the maximum size of the request that the NFS client generates.
Data Type	Unsigned integer (32-bit)
Default	32,768 (32 KB)

Range	0 to $2^{32} - 1$
Units	Bytes
Dynamic?	Yes, but this parameter is set per file system at mount time. To affect a particular file system, unmount and mount the file system after changing this parameter.
Validation	<p>None. However, setting the maximum transfer size on the NFS server to 0 is likely to cause FS clients to malfunction or just decide not to attempt to talk to the server.</p> <p>There is also a limit on the maximum transfer size when using NFS over the UDP transport. For more information about the maximum for UDP, see “nfs:nfs3_max_transfer_size Parameter” on page 116.</p>
When to Change	<p>To tune the size of data transmitted over the network. In general, the “nfs:nfs4_bsize Parameter” on page 103 parameter should also be updated to reflect changes in this parameter.</p> <p>For example, when you attempt to increase the transfer size beyond 32 KB, update <code>nfs:nfs4_bsize</code> to reflect the increased value. Otherwise, no change in the over-the-wire request size is observed.</p> <p>If you want to use a smaller transfer size than the default transfer size, use the mount command's <code>-wsize -rsize</code> option on a per-file system basis.</p>
Commitment Level	Unstable

nfs:nfs3_max_transfer_size_clts Parameter

Description	Controls the maximum size of the data portion of an NFS version 3 READ, WRITE, REaddir, or REaddirplus request over UDP. This parameter controls both the maximum size of the request that the NFS server returns as well as the maximum size of the request that the NFS client generates.
Data Type	Unsigned integer (32-bit)
Default	32,768 (32 KB)
Range	0 to $2^{32} - 1$

Units	Bytes
Dynamic?	Yes, but this parameter is set per file system at mount time. To affect a particular file system, unmount and mount the file system after changing this parameter.
Validation	None. However, setting the maximum transfer size on the NFS server to 0 is likely to cause NFS clients to malfunction or just decide not to attempt to talk to the server.
When to Change	Do not change this parameter.
Commitment Level	Unstable

nfs:nfs3_max_transfer_size_cots Parameter

Description	Controls the maximum size of the data portion of an NFS version 3 READ, WRITE, REaddir, or REaddirplus request over TCP. This parameter controls both the maximum size of the request that the NFS server returns as well as the maximum size of the request that the NFS client generates.
Data Type	Unsigned integer (32-bit)
Default	1,048,576 bytes (1MB)
Range	0 to $2^{32} - 1$
Units	Bytes
Dynamic?	Yes, but this parameter is set per file system at mount time. To affect a particular file system, unmount and mount the file system after changing this parameter.
Validation	None. However, setting the maximum transfer size on the NFS server to 0 is likely to cause NFS clients to malfunction or just decide not to attempt to talk to the server.
When to Change	Do not change this parameter unless transfer sizes larger than 1 MB are preferred.
Commitment Level	Unstable

nfs:nacache Parameter

Description	Tunes the number of hash queues that access the file access cache on the NFS client. The file access cache stores file access rights that users have with respect to files that they are trying to access. The cache itself is dynamically allocated. However, the hash queues used to index into the cache are statically allocated. The algorithm assumes that there is one access cache entry per active file and four of these access cache entries per hash bucket. Thus, by default, the value of this parameter is set to the value of the “ nfs:nrnode Parameter ” on page 123 parameter.
Data Type	Integer (32-bit)
Default	The default setting of this parameter is 0. This value means that the value of nacache should be set to the value of the nrnode parameter.
Range	1 to $2^{31} - 1$
Units	Access cache entries
Dynamic?	No. This value can only be changed by adding or changing the parameter in an <code>/etc/system.d/file</code> , and then rebooting system.
Validation	None. However, setting this parameter to a negative value will probably cause the system to try to allocate a very large set of hash queues. While trying to do so, the system is likely to hang.
When to Change	Examine the value of this parameter if the basic assumption of one access cache entry per file would be violated. This violation could occur for systems in a timesharing mode where multiple users are accessing the same file at about the same time. In this case, it might be helpful to increase the expected size of the access cache so that the hashed access to the cache stays efficient.
Commitment Level	Unstable

nfs:nfs_nra Parameter

Description	Controls the number of read-ahead operations that are queued by the NFS version 2 client when sequential access to a file is discovered. These
-------------	--

	read-ahead operations increase concurrency and read throughput. Each read-ahead request is generally for one logical block of file data.
Data Type	Integer (32-bit)
Default	4
Range	0 to $2^{31} - 1$
Units	Logical blocks.
Dynamic?	Yes
Validation	None
When to Change	To increase or reduce the number of read-ahead requests that are outstanding for a specific file at any given time. For example, for a very low bandwidth network or on a low memory client, you might want to decrease this value so that the NFS client does not overload the network or the system memory. Alternately, if the network is very high bandwidth, and the NFS client and NFS server have sufficient resources, you might want to increase this value. Doing so can more effectively utilize the available network bandwidth, and the client and server resources.
Commitment Level	Unstable

nfs:nfs3_nra Parameter

Description	Controls the number of read-ahead operations that are queued by the NFS version 3 client when sequential access to a file is discovered. These read-ahead operations increase concurrency and read throughput. Each read-ahead request is generally for one logical block of file data.
Data Type	Integer (32-bit)
Default	4
Range	0 to $2^{31} - 1$
Units	Logical blocks. (See “nfs:nfs3_bsize Parameter” on page 102.)

Dynamic?	Yes
Validation	None
When to Change	To increase or reduce the number of read-ahead requests that are outstanding for a specific file at any given time. For example, for a very low bandwidth network or on a low memory client, you might want to decrease this value so that the NFS client does not overload the network or the system memory. Alternately, if the network is very high bandwidth and the NFS client and NFS server have sufficient resources, you might want to increase this value. Doing so can more effectively utilize the available network bandwidth, and the client and server resources.
Commitment Level	Unstable

nfs:nfs4_nra Parameter

Description	Controls the number of read-ahead operations that are queued by the NFS version 4 client when sequential access to a file is discovered. These read-ahead operations increase concurrency and read throughput. Each read-ahead request is generally for one logical block of file data.
Data Type	Integer (32-bit)
Default	4
Range	0 to $2^{31} - 1$
Units	Logical blocks. (See " nfs:nfs3_bsize Parameter" on page 102.)
Dynamic?	Yes
Validation	None
When to Change	To increase or reduce the number of read-ahead requests that are outstanding for a specific file at any given time. For example, for a very low bandwidth network or on a low memory client, you might want to decrease this value so that the NFS client does not overload the network or the system memory. Alternately, if the network is very high bandwidth and the NFS client and NFS server have sufficient resources, you might want to increase this value. Doing so can more effectively utilize the available network bandwidth, and the client and server resources.

Commitment Level Unstable

nfs:nrnode Parameter

Description	<p>Controls the size of the <code>nrnode</code> cache on the NFS client.</p> <p>The <code>nrnode</code>, used by NFS version 2, 3, and 4 clients, is the central data structure that describes a file on the NFS client. The <code>nrnode</code> contains the file handle that identifies the file on the NFS server. The <code>nrnode</code> also contains pointers to various caches used by the NFS client to avoid network calls to the server. Each <code>nrnode</code> has a one-to-one association with a <code>vrnode</code>. The <code>vrnode</code> caches file data.</p> <p>The NFS client attempts to maintain a minimum number of <code>nrnodes</code> to attempt to avoid destroying cached data and metadata. When an <code>nrnode</code> is reused or freed, the cached data and metadata must be destroyed.</p>
Data Type	Integer (32-bit)
Default	The default setting of this parameter is 0, which means that the value <code>nrnode</code> should be set to the value of the <code>ncsize</code> parameter. Actually, any non positive value of <code>nrnode</code> results in <code>nrnode</code> being set to the value of <code>ncsize</code> .
Range	1 to $2^{31} - 1$
Units	<code>nrnodes</code>
Dynamic?	No. This value can only be changed by adding or changing the parameter in an <code>/etc/system.d/file</code> , and then rebooting the system.
Validation	The system enforces a maximum value such that the <code>nrnode</code> cache can only consume 25 percent of available memory.
When to Change	Because <code>nrnodes</code> are created and destroyed dynamically, the system tends to settle upon a <code>nrnode</code> -size cache, automatically adjusting the size of the cache as memory pressure on the system increases or as more files are simultaneously accessed. However, in certain situations, you could set the value of <code>nrnode</code> if the mix of files being accessed can be predicted in advance. For example, if the NFS client is accessing a few very large files, you could set the value of <code>nrnode</code> to a small number so that system memory can cache file data instead of <code>nrnodes</code> . Alternately, if the client

is accessing many small files, you could increase the value of `nrnode` to optimize for storing file metadata to reduce the number of network calls for metadata.

Although it is not recommended, the `rnode` cache can be effectively disabled by setting the value of `nrnode` to 1. This value instructs the client to only cache 1 `rnode`, which means that it is reused frequently.

Commitment Level Unstable

nfs:nfs3_pathconf_disable_cache Parameter

Description	Controls the caching of pathconf information for NFS Version 3 mounted file systems.
Data Type	Integer (32-bit)
Default	0 (caching enabled)
Range	0 (caching enabled) or 1 (caching disabled)
Units	Boolean values
Dynamic?	Yes
Validation	None
When to Change	The pathconf information is cached on a per file basis. However, if the NFS server can change the information for a specific file dynamically, use this parameter to disable caching. There is no mechanism for the NFS client to validate its cache entry.
Commitment Level	Unstable

nfs:nfs_shrinkreaddir Parameter

Description	Some older NFS servers might incorrectly handle NFS version 2 REaddir requests for more than 1024 bytes of directory information. This problem is due to a bug in the server implementation. However, this parameter contains a workaround in the NFS version 2 client.
-------------	---

When this parameter is enabled, the client does not generate REaddir request for larger than 1024 bytes of directory information. If this parameter is disabled, then the over-the-wire size is set to the lesser of either the size passed in by using the `getdents` system call or by using `NFS_MAXDATA`, which is 8192 bytes. For more information, see [getdents\(2\)](#).

Data Type	Integer (32-bit)
Default	0 (disabled)
Range	0 (disabled) or 1 (enabled)
Units	Boolean values
Dynamic?	Yes
Validation	None
When to Change	Examine the value of this parameter if an older NFS version 2 only server is used and interoperability problems occur when the server tries to read directories. Enabling this parameter might cause a slight decrease in performance for applications that read directories.
Commitment Level	Unstable

nfs:nfs3_shrinkreaddir Parameter

Description Some older NFS servers might incorrectly handle NFS version 3 REaddir requests for more than 1024 bytes of directory information. This problem is due to a bug in the server implementation. However, this parameter contains a workaround in the NFS version 3 client.

When this parameter is enabled, the client does not generate REaddir request for larger than 1024 bytes of directory information. If this parameter is disabled, then the over-the-wire size is set to the minimum of either the size passed in by using the `getdents` system call or by using `MAXBSIZE`, which is 8192 bytes. For more information, see the [getdents\(2\)](#) man page.

Data Type	Integer (32-bit)
-----------	------------------

Default	0 (disabled)
Range	0 (disabled) or 1 (enabled)
Units	Boolean values
Dynamic?	Yes
Validation	None
When to Change	Examine the value of this parameter if an older NFS version 3 only server is used and interoperability problems occur when the server tries to read directories. Enabling this parameter might cause a slight decrease in performance for applications that read directories.
Commitment Level	Unstable

nfs:nfs_write_error_interval Parameter

Description	Controls the time duration in between logging ENOSPC and EDQUOT write errors received by the NFS client. This parameter affects NFS version 2, 3, and 4 clients.
Data Type	Long integer (64-bit)
Default	5 seconds
Range	0 to $2^{63} - 1$
Units	Seconds
Dynamic?	Yes
Validation	None
When to Change	Increase or decrease the value of this parameter in response to the volume of messages being logged by the NFS client. Typically, you might want to increase the value of this parameter to decrease the number of out of space messages being printed when a full file system on a NFS server is being actively used.
Commitment Level	Unstable

nfs:nfs_write_error_to_cons_only Parameter

Description	Controls whether NFS write errors are logged to the system console and <code>syslog</code> or to the system console only. This parameter affects messages for NFS version 2, 3, and 4 clients.
Data Type	Integer (32-bit)
Default	0 (system console and <code>syslog</code>)
Range	0 (system console and <code>syslog</code>) or 1 (system console)
Units	Boolean values
Dynamic?	Yes
Validation	None
When to Change	Examine the value of this parameter to avoid filling up the file system containing the messages logged by the <code>syslogd</code> daemon. When this parameter is enabled, messages are printed on the system console only and are not copied to the <code>syslog</code> messages file.
Commitment Level	Unstable

NFS-Related SMF Configuration Parameters

In Oracle Solaris 11.2, the `network/nfs/server` service includes the `nfs-props` property group, which provides configurable parameters to control the refresh of the NFS authentication cache and to control the `mountd` netgroup cache.

- [“server_authz_cache_refresh Parameter” on page 128](#)
- [“netgroup_refresh Parameter” on page 128](#)

You can use `sharectl` command to get and set these properties.

```
# sharectl get -p server_authz_cache_refresh nfs
server_authz_cache_refresh=600
$ sharectl set -p server_authz_cache_refresh=1 nfs
```

You can also get and set these properties by using SMF commands but you will need to refresh the `network/nfs/server` service.

```
# svccfg -s nfs/server:default setprop nfs-props/server_authz_cache_refresh=1
# svcprop -p nfs-props/server_authz_cache_refresh svc:/network/nfs/server:default
1
# svcadm restart nfs/server:default
```

server_authz_cache_refresh Parameter

This parameter controls the refresh of the NFS authentication cache. The default value of the integer property is 600, the minimum is 0, and the max is INT32_MAX. A value of zero (0) means no expiration.

netgroup_refresh Parameter

This parameter controls the mountd netgroup cache. The default value of the integer property is 600, the minimum is 0, and the max is INT32_MAX. A value of zero (0) means no expiration.

nfssrv Module Parameters

This section describes NFS parameter for the `nfssrv` module.

nfssrv:rfs_write_async Parameter

Description	<p>Controls the behavior of the NFS version 2 server when it processes WRITE requests. The NFS version 2 protocol mandates that all modified data and metadata associated with the WRITE request reside on stable storage before the server can respond to the client. NFS version 2 WRITE requests are limited to 8192 bytes of data. Thus, each WRITE request might cause multiple small writes to the storage subsystem. This can cause a performance problem.</p> <p>One method to accelerate NFS version 2 WRITE requests is to take advantage of a client behavior. Clients tend to send WRITE requests in batches. The server can take advantage of this behavior by clustering together the different WRITE requests into a single request to the underlying file system. Thus, the data to be written to the storage subsystem can be written in fewer, larger requests. This method can significantly increase the throughput for WRITE requests.</p>
-------------	---

Data Type	Integer (32-bit)
Default	1 (clustering enabled)
Range	0 (clustering disabled) or 1 (clustering enabled)
Units	Boolean values
Dynamic?	Yes
Validation	None
When to Change	Some very small NFS clients, particularly PC clients, might not batch WRITE requests. Thus, the behavior required from the clients might not exist. In addition, the clustering in the NFS version 2 server might just add overhead and slow down performance instead of increasing it.
Commitment Level	Unstable

rpcmod Module Parameters

This section describes NFS parameters for the rpcmod module.

rpcmod:clnt_max_conns Parameter

Description	Controls the number of TCP connections that the NFS client uses when communicating with each NFS server. The kernel RPC is constructed so that it can multiplex RPCs over a single connection. However, multiple connections can be used, if preferred.
Data Type	Integer (32-bit)
Default	1
Range	1 to $2^{31} - 1$
Units	Connections
Dynamic?	Yes

Validation	None
When to Change	<p>In general, one connection is sufficient to achieve full network bandwidth. However, if TCP cannot utilize the bandwidth offered by the network in a single stream, then multiple connections might increase the throughput between the NFS client and the NFS server.</p> <p>Increasing the number of connections doesn't come without consequences. Increasing the number of connections also increases kernel resource usage needed to keep track of each connection.</p>
Commitment Level	Unstable

rpcmod:clnt_idle_timeout Parameter

Description	Controls the duration of time on the NFS client that a connection between the NFS client and NFS server is allowed to remain idle before being closed.
Data Type	Long integer (64-bit)
Default	300,000 milliseconds (5 minutes)
Range	0 to $2^{63} - 1$
Units	Milliseconds
Dynamic?	Yes
Validation	None
When to Change	Use this parameter to change the time that idle connections are allowed to exist on the NFS client before being closed. You might want to close connections at a faster rate to avoid consuming system resources.
Commitment Level	Unstable

rpcmod:svc_idle_timeout Parameter

Description	Controls the duration of time on the NFS server that a connection between the NFS client and NFS server is allowed to remain idle before being closed.
-------------	--

Data Type	Long integer (64-bit)
Default	360,000 milliseconds (6 minutes)
Range	0 to $2^{63} - 1$
Units	Milliseconds
Dynamic?	Yes
Validation	None
When to Change	Use this parameter to change the time that idle connections are allowed to exist on the NFS server before being closed. You might want to close connections at a faster rate to avoid consuming system resources.
Commitment Level	Unstable

Internet Protocol Suite Tunable Parameters

This chapter describes various Internet Protocol (IP) suite properties.

- “IP Tunable Parameters”
- “TCP Tunable Parameters”
- “UDP Tunable Parameters”
- “SCTP Tunable Parameters”
- “ICMP Tunable Parameters”
- “Per-Route Metrics”

For other types of tunable parameters, refer to the following information:

- Oracle Solaris kernel tunable parameters – [Chapter 2, “Oracle Solaris Kernel Tunable Parameters”](#)
- Oracle Solaris ZFS tunable parameters – [Chapter 3, “Oracle Solaris ZFS Tunable Parameters”](#)
- NFS tunable parameters – [Chapter 4, “NFS Tunable Parameters”](#)
- System facility tunable parameters – [Chapter 6, “System Facility Parameters”](#)

Overview of Tuning IP Suite Parameters

You can set all of the tuning parameters that are described in this chapter by using the following `ipadm` command syntax:

```
$ ipadm set-prop -p parameter ip|ipv4|ipv6|tcp|udp|sctp
```

For example, you would set the `extra-priv-ports` tunable parameter as follows:

```
$ ipadm set-prop -p extra-priv-ports=1047 tcp
```

PROTO	PROPERTY	PERM	CURRENT	PERSISTENT	DEFAULT	POSSIBLE
tcp	extra-priv-ports	rw	1047	1047	2049,4045	1-65535

For more information, see the [ipadm\(8\)](#) man page.

IP Suite Parameter Validation

All of the parameters that are described are checked to verify that they fall in the parameter range. The parameter's range is provided with the description for each parameter.

Internet Request for Comments

Internet protocol and standard specifications are described in Internet Request for Comments (RFC) documents at <http://www.ietf.org/rfc.html>.

To review RFC topics, type the RFC number or an Internet-draft file name in the Internet Engineering Task Force (IETF) Repository Retrieval search field.

IP Tunable Parameters

This section describes parameters pertaining to the IP protocol.

`_addrs_per_if` Parameter

Description	Defines the maximum number of logical IP interfaces associated with a real interface. Each logical interface in the Oracle Solaris kernel maps to a single IP address.
Default	256
Range	1 to 8,192
Dynamic?	Yes
When to Change	Do not change the value. If more logical interfaces are required, you might consider increasing the value. However, recognize that this change might have a negative impact on IP's performance.
Commitment Level	Unstable

`_forwarding_src_routed` Parameter (IPv4 or IPv6)

Description	Controls whether IPv4 or IPv6 forwards packets with source IPv4 routing options or IPv6 routing headers.
Default	Off
Range	Off or On
Dynamic?	Yes
When to Change	Keep this parameter disabled to prevent denial of service attacks.
Commitment Level	Unstable

`_icmp_err_interval` and `_icmp_err_burst` Parameters

Description	<p>Controls the rate of IP in generating ICMP error messages. IP generates only up to <code>_icmp_err_burst</code> IP error messages in any <code>_icmp_err_interval</code>.</p> <p>The <code>_icmp_err_interval</code> parameter protects IP from denial of service attacks. Setting this parameter to 0 disables rate limiting. It does not disable the generation of error messages.</p>
Default	<p>100 milliseconds for <code>_icmp_err_interval</code></p> <p>10 error messages for <code>_icmp_err_burst</code></p>
Range	<p>0 – 99,999 milliseconds for <code>_icmp_err_interval</code></p> <p>1 – 99,999 error messages for <code>_icmp_err_burst</code></p>
Dynamic?	Yes
When to Change	If you need a higher error message generation rate for diagnostic purposes.
Commitment Level	Unstable

`_policy_mask` Parameter

Description Enables or disables IPQoS processing in any of the following callout positions: forward outbound, forward inbound, local outbound, and local inbound. This parameter is a bitmask as follows:

Not Used	Not Used	Not Used	Not Used	Forward Outbound	Forward Inbound	Local Outbound	Local Inbound
X	X	X	X	0	0	0	0

A 1 in any of the position masks or disables IPQoS processing in that particular callout position. For example, a value of `0x01` disables IPQoS processing for all the local inbound packets.

Default The default value is 0, meaning that IPQoS processing is enabled in all the callout positions.

Range 0 (0x00) to 15 (0x0F). A value of 15 indicates that IPQoS processing is disabled in all the callout positions.

Dynamic? Yes

When to Change If you want to enable or disable IPQoS processing in any of the callout positions.

Commitment Level Unstable

`_respond_to_echo_broadcast (IP)` and `_respond_to_echo_multicast` Parameters (IPv4 or IPv6)

Description Controls whether IP responds to a broadcast ICMPv4 echo request or a multicast ICMPv4 or ICMPv6 echo request.

Default 1 (enabled)

Range 0 (disabled) or 1 (enabled)

Dynamic?	Yes
When to Change	If you do not want this behavior for security reasons, disable it.
Commitment Level	Unstable

hoplimit Parameter (IPv6)

Description	<p>Sets the value of the hop limit in the IPv6 header for the outbound ICMPv6 error and reply packets. The hop limit defines the maximum number of routers a packet can pass through on the path to the destination. It is primarily used to clear messages from the network when a misconfiguration would otherwise cause messages to endlessly loop through the same set of routers.</p> <p>The hoplimit set on outbound ICMP requests and on UDP, TCP, and SCTP messages is not controlled by this property. It is instead controlled by the <code>_ipv6_hoplimit</code> property for each respective protocol.</p>
Default	255
Range	1 to 255
Dynamic?	Yes
When to Change	Generally, you do not need to change this value.
Commitment Level	Stable

hostmodel Parameter (IPv4 or IPv6)

Description	Controls send and receive behavior for IPv4 or IPv6 packets on a multi-homed system.
Default	weak
Range	<p>weak, strong, or src-priority</p> <ul style="list-style-type: none"> ■ weak <ul style="list-style-type: none"> ■ Outgoing packets - The source address of the packet going out need not match the address configured on the outgoing interface.

- Incoming packets - The destination address of the incoming packet need not match the address configured on the incoming interface.
- `strong`
 - Outgoing packets - The source address of the packet going out must match the address configured on the outgoing interface.
 - Incoming packets - The destination address of the incoming packet must match the address configured on the incoming interface.
- `src-priority`
 - Outgoing packets - If multiple routes for the IP destination in the packet are available, the system prefers routes where the IP source address in the packet is configured on the outgoing interface.

If no such route is available, the system falls back to selecting the *best* route, as with the weak ES case.
 - Incoming packets - The destination address of the incoming packet must be configured on any one of the host's interface.

Dynamic?	Yes
When to Change	If a system has interfaces that cross strict networking domains (for example, a firewall or a VPN node), set this parameter to <code>strong</code> .
Commitment Level	Stable

recv-multicast-scaling Parameter

Description	Defines system-wide default value to enable receiving multicast packets through a more scalable data path that uses extra worker threads to deliver multicast packets. Multicast applications are usually streaming data type, where packets are small but the packet rate can be very high. The normal data path cannot handle very high packet rate without drops. This problem is especially acute when there are multiple receivers for the same multicast group. However, for the general case, there might be a tradeoff between latency and scalability.
Default	0 (off)
Range	0 (off) or 1 (on)

Dynamic?	Yes
When to Change	Change from the default setting in cases of high volume of UDP multicast traffic.
Commitment Level	Stable

send-redirects Parameter (IPv4 or IPv6)

Description	Controls whether IPv4 or IPv6 sends out ICMPv4 or ICMPv6 redirect messages.
Default	1 (enabled)
Range	0 (disabled) or 1 (enabled)
Dynamic?	Yes
When to Change	If you do not want this behavior for security reasons, disable it.
Commitment Level	Stable

ttl Parameter (IPv4)

Description	<p>Controls the time to live (TTL) value in the IPv4 header for the outbound IPv4 ICMP error and reply packets. The TTL defines the maximum number of routers a packet can pass through on the path to the destination. It is primarily used to clear messages from the network when a misconfiguration would otherwise cause messages to endlessly loop through the same set of routers.</p> <p>The <code>ttl</code> set on outbound ICMP requests and on UDP, TCP, and SCTP messages is not controlled by this property. It is instead controlled by the “_ipv4_ttl Parameter” property for each respective protocol.</p>
Default	255
Range	1 to 255
Dynamic?	Yes
When to Change	Generally, you do not need to change this value.

Commitment Level Stable

IP Tunable Parameters Related to Duplicate Address Detection

The following parameters can be configured to perform duplicate address detection (DAD) in the network.

`_arp_defend_interval/_ndp_defend_interval` Parameter

Description	Interval in which the system continues to broadcast announcements for a specific address using IPv4 ARP and IPv6 NDP, respectively, to detect duplicate addresses in the network after the initial duplicate address detection process completes successfully.
Default	300,000 milliseconds
Range	0-360,000
Dynamic?	Yes
When to Change	Never
Commitment Level	Unstable

`_arp_defend_period/_ndp_defend_period` Parameter

Description	<p>Time period within which unrequested address-defense ARP or NDP messages are generated on any one physical network interface. These parameters work together with “_arp_defend_rate/_ndp_defend_rate Parameter”.</p> <p>These parameters does not apply to normal ARP or NDP resolution or to address defense due to detected conflicts. Rather, the parameters are implemented only on unbidden conflict detection traffic.</p>
Default	3,600 seconds
Range	0-3,600

Dynamic?	Yes
When to Change	Never
Commitment Level	Unstable

_arp_defend_rate/_ndp_defend_rate Parameter

Description	<p>Number of unrequested address-defense ARP or NDP messages that can be generated in an hour period on any one physical network interface. The time period can be revised by configuring “_arp_defend_period/_ndp_defend_period Parameter”.</p> <p>The <code>_arp_defend_rate/_ndp_defend_rate</code> work together with the <code>_arp_defend_period/_ndp_defend_period</code> to prevent a system with a large number of configured IP addresses from flooding the network with ARP traffic.</p> <p>By default, the system will continuously broadcast an ARP announcement or NDP advertisement every five minutes for each address that already passed duplicate address detection. However, the total number of such ARP announcements or NDP advertisements from an interface is further limited to 100 messages per hour regardless of the number of configured addresses.</p> <p>These parameters does not apply to normal ARP or NDP resolution nor to address defense due to detected conflicts. Rather, the parameters are implemented only on unbidden conflict detection traffic.</p>
Default	100 messages/hour
Range	0-20,000
Dynamic?	Yes
When to Change	Never
Commitment Level	Unstable

_arp_fastprobe_count Parameter

Description	In a transmit-pause sequence, the number of probes that are transmitted to detect duplicate addresses before pausing. The length of time is
-------------	---

defined in “[_arp_fastprobe_interval Parameter](#)”. The parameter is used for faster probing for duplicate addresses.

Default	3 packets
Range	0-20
Dynamic?	Yes
When to Change	Never
Commitment Level	Unstable

_arp_fastprobe_interval Parameter

Description	Similar function to “ _arp_probe_interval Parameter ”, which is the time between the sending of a set number of probes to detect duplicate addresses. To accelerate the process in bringing up an IP interface, and if the underlying driver can properly report link up or link down events, the system uses this parameter as the interval between sending out probes. This parameter works together with “ _arp_fastprobe_count Parameter ”.
Default	150 milliseconds
Range	10-20,000
Dynamic?	Yes
When to Change	Never
Commitment Level	Unstable

_arp_probe_count Parameter

Description	In a transmit-pause sequence, the number of probes that are transmitted to detect duplicate addresses before pausing. The length of the pause is determined by “ _arp_probe_interval Parameter ”. After the pause time expires, probing resumes.
Default	3 packets

Range	0-20
Dynamic?	Yes
When to Change	Never
Commitment Level	Unstable

_arp_probe_interval Parameter

Description	Time between the sending of a set number of probes to detect duplicate addresses. The number of probes that is sent after each interval is defined in “ _arp_probe_count Parameter ”.
Default	1,500 milliseconds
Range	10-20,000
Dynamic?	Yes
When to Change	Never
Commitment Level	Unstable

_defend_interval Parameter

Description	Length of time a system defends its local address when it is detected to be in conflict with another system's IP address. The number of attempts to defend the address within this period is defined in “ _max_defend Parameter ”.
Default	30 seconds
Range	0-999,999
Dynamic?	Yes
When to Change	Never
Commitment Level	Unstable

`_dup_recovery` Parameter

Description	Time between the transmission of probes after the system marks a non-temporary address down because it conflicts with the same address in a remote system. The local system sends out probes periodically to test whether the conflict persists. If the probe receives no reply, the conflict is considered cleared and the address is marked up again.
Default	300,000 milliseconds
Range	0-360,000
Dynamic?	Yes
When to Change	Never
Commitment Level	Unstable

`_max_defend` Parameter

Description	The number of times an IP address is defended if the address conflicts with another system's IP address. Defense of the address occurs within the time specified in " _defend_interval Parameter".
Default	3 counts
Range	0-1,000
Dynamic?	Yes
When to Change	Never
Commitment Level	Unstable

`_max_temp_defend` Parameter

Description	Number of times a system defends a temporary local address or a DHCP controlled address when that address is in conflict with another system's IP address. When the value of <code>_max_temp_defend</code> is passed, the system gives up the address.
-------------	--

Default	1 count
Range	0-1,000
Dynamic?	Yes
When to Change	Never
Commitment Level	Unstable

arp-publish-count/ndp-unsolicit-count Parameter

Description	Number of unsolicited IPv4 ARP announcements or IPv6 NDP advertisements transmitted over an interface to update the address cache of network peers. The announcements are sent after a local IP address has been successfully brought up and are transmitted at intervals controlled by the “arp-publish-interval/ndp-unsolicit-interval Parameter” parameters.
Default	3 packets
Range	1-20
Dynamic?	Yes
When to Change	Never
Commitment Level	Stable

arp-publish-interval/ndp-unsolicit-interval Parameter

Description	Time between successive unsolicited IPv4 ARP announcements or IPv6 NDP advertisements that are sent after a local IP address is successfully brought up. The announcements are sent to update the address cache of network peers.
Default	2,000 milliseconds
Range	1,000-20,000
Dynamic?	Yes

When to Change	Never
Commitment Level	Stable

IP Tunable Parameters With Additional Cautions

Changing the following parameters is not recommended.

`_icmp_return_data_bytes` Parameter (IPv4 or IPv6)

Description	When IPv4 or IPv6 sends an ICMPv4 or ICMPv6 error message, it includes the IP header of the packet that caused the error message. This parameter controls how many extra bytes of the packet beyond the IPv4 or IPv6 header are included in the ICMPv4 or ICMPv6 error message.
Default	64 for IPv4 1,280 for IPv6
Range	8-65,536 for IPv4 8-1,280 for IPv6
Dynamic?	Yes
When to Change	Do not change the value. Including more information in an ICMP error message might help in diagnosing network problems. If this feature is needed, increase the value.
Commitment Level	Unstable

`_pathmtu_interval` Parameter

Description	Specifies the interval in milliseconds at which IP flushes the path maximum transfer unit (PMTU) discovery information, and tries to rediscover PMTU. Refer to RFC 1191 on PMTU discovery.
Default	1,200 milliseconds (20 minutes)
Range	2-999,999,999

Dynamic?	Yes
When to Change	Do not change this value.
Commitment Level	Unstable

TCP Tunable Parameters

This section describes parameters specific to the TCP transport protocol.

`_conn_req_max_q` Parameter

Description	Specifies the default maximum number of pending TCP connections for a TCP listener waiting to be accepted by <code>accept()</code> . See also “_conn_req_max_q0 Parameter” .
Default	128
Range	1 to 4,294,967,295
Dynamic?	Yes
When to Change	<p>For applications such as web servers that might receive several connection requests, the default value might be increased to match the incoming rate.</p> <p>Do not increase the parameter to a very large value. The pending TCP connections can consume excessive memory. Also, if an application cannot handle that many connection requests fast enough because the number of pending TCP connections is too large, new incoming requests might be denied.</p> <p>Note that increasing <code>_conn_req_max_q</code> does not mean that applications can have that many pending TCP connections. Applications can use <code>listen()</code> to change the maximum number of pending TCP connections for each socket. This parameter is the maximum an application can use <code>listen()</code> to set the number to. Thus, even if this parameter is set to a very large value, the actual maximum number for a socket might be much less than <code>_conn_req_max_q</code>, depending on the value used in <code>listen()</code>.</p>

Commitment Level Unstable

`_conn_req_max_q0` Parameter

Description Specifies the default maximum number of incomplete (three-way handshake not yet finished) pending TCP connections for a TCP listener. For more information about TCP three-way handshake, refer to RFC 793. See also “[_conn_req_max_q Parameter](#)”.

Default 1,024

Range 0 to 4,294,967,295

Dynamic? Yes

When to Change For applications such as web servers that might receive excessive connection requests, you can increase the default value to match the incoming rate.

The following explains the relationship between `_conn_req_max_q0` and the maximum number of pending connections for each socket.

When a connection request is received, TCP first checks if the number of pending TCP connections (three-way handshake is done) waiting to be accepted exceeds the maximum (*N*) for the listener. If the connections are excessive, the request is denied. If the number of connections is allowable, then TCP checks if the number of incomplete pending TCP connections exceeds the sum of *N* and `_conn_req_max_q0`. If it does not, the request is accepted. Otherwise, the oldest incomplete pending TCP request is dropped.

Commitment Level Unstable

`_conn_req_min` Parameter

Description Specifies the default minimum value for the maximum number of pending TCP connection requests for a listener waiting to be accepted. This is the lowest maximum value of `listen()` that an application can use.

Default 1

Range	1 to 1,024
Dynamic?	Yes
When to Change	This parameter can be a solution for applications that use <code>listen()</code> to set the maximum number of pending TCP connections to a value too low. Increase the value to match the incoming connection request rate.
Commitment Level	Unstable

`_deferred_ack_interval` Parameter

Description	Specifies the time-out value for the TCP-delayed acknowledgment (ACK) timer for stems that are not directly connected. Refer to RFC 1122, 4.2.3.2.
Default	100 milliseconds
Range	1 millisecond to 60,000 milliseconds
Dynamic?	Yes
When to Change	Do not increase this value to more than 500 milliseconds. Increase the value under the following circumstances: <ul style="list-style-type: none"> ▪ Slow network links (less than 57.6 Kbps) with greater than 512 bytes maximum segment size (MSS) ▪ The interval for receiving more than one TCP segment is short
Commitment Level	Unstable

`_deferred_acks_max` Parameter

Description	Specifies the maximum number of TCP segments received from remote destinations (not the same subnet) before an acknowledgment (ACK) is generated. TCP segments are measured in units of maximum segment size (MSS) for individual connections. If set to 0 or 1, no ACKs are delayed, assuming all segments are 1 MSS long. The actual number is dynamically calculated for each connection. The value is the default maximum.
-------------	--

Default	2
Range	0 to 16
Dynamic?	Yes
When to Change	This parameter should not be changed in normal circumstances.
Commitment Level	Unstable

_ipv4_ttl Parameter

Description	Controls the time to live (TTL) value in the IPv4 header for outbound TCP messages sent over IPv4. For more information, see the description for “ttl Parameter (IPv4)” .
Default	64 bytes
Range	1 to 255
Dynamic?	Yes
When to Change	Do not change this value in a normal network environment.
Commitment Level	Unstable

_ipv6_hoplimit Parameter

Description	Sets the value of the hop limit in the IPv6 header for the outbound TCP messages sent over IPv6. For more information, see the description for “hoplimit Parameter (IPv6)” .
Default	60
Range	1 to 255
Dynamic?	Yes
When to Change	Do not change this value in a normal network environment.
Commitment Level	Unstable

`_local_dack_interval` Parameter

Description	Specifies the time-out value for TCP-delayed acknowledgment (ACK) timer for stems that are directly connected. Refer to RFC 1122, 4.2.3.2.
Default	50 milliseconds
Range	10 milliseconds to 500 milliseconds
Dynamic?	Yes
When to Change	Do not increase this value to more than 500 milliseconds. Increase the value under the following circumstances: <ul style="list-style-type: none"> ■ Slow network links (less than 57.6 Kbps) with greater than 512 bytes maximum segment size (MSS) ■ The interval for receiving more than one TCP segment is short
Commitment Level	Unstable

`_local_dacks_max` Parameter

Description	Specifies the maximum number of TCP segments received from peers on the same subnet before an acknowledgment (ACK) is generated. TCP segments are measured in units of maximum segment size (MSS) for individual connections. If set to 0 or 1, it means no ACKs are delayed, assuming all segments are 1 MSS long. The actual number is dynamically calculated for each connection. The value is the default maximum.
Default	8
Range	0 to 16
Dynamic?	Yes
When to Change	Do not change the value. In some circumstances, when the network traffic becomes very bursty because of the delayed ACK effect, decrease the value. Do not decrease this value below 2.
Commitment Level	Unstable

`_local_slow_start_initial` Parameter

Description	Defines the initial congestion window size in the maximum segment size (MSS) of a TCP connection between systems on the same subnet.
Default	10
Range	1 to 16,384
Dynamic?	Yes
When to Change	Consider increasing this parameter value if applications would benefit from a larger initial window.
Commitment Level	Unstable

`_rev_src_routes` Parameter

Description	If set to 0, TCP does not reverse the IP source routing option for incoming connections for security reasons. If set to 1, TCP does the normal reverse source routing.
Default	0 (disabled)
Range	0 (disabled) or 1 (enabled)
Dynamic?	Yes
When to Change	If IP source routing is needed for diagnostic purposes, enable it.
Commitment Level	Unstable

`_rst_sent_rate` Parameter

Description	Sets the maximum number of RST segments that TCP can send out per second.
Default	40
Range	0 to 4,294,967,295

Dynamic?	Yes
When to Change	In a TCP environment, there might be a legitimate reason to generate more RSTs than the default value allows. In this case, increase the default value of this parameter.
Commitment Level	Unstable

`_rst_sent_rate_enabled` Parameter

Description	If this parameter is set to 1, the maximum rate of sending a RST segment is controlled by the <code>ipadm</code> parameter, <code>_rst_sent_rate</code> . If this parameter is set to 0, no rate control when sending a RST segment is available.
Default	1 (enabled)
Range	0 (disabled) or 1 (enabled)
Dynamic?	Yes
When to Change	This tunable helps defend against denial of service attacks on TCP by limiting the rate by which a RST segment is sent out. The only time this rate control should be disabled is when strict conformance to RFC 793 is required.
Commitment Level	Unstable

`_slow_start_after_idle` Parameter

Description	The congestion window size in the maximum segment size (MSS) of a TCP connection after it has been idled (no segment received) for a period of one retransmission timeout (RTO). Refer to RFC 2414 on how the initial congestion window size is calculated.
Default	4
Range	1 to 16,384
Dynamic?	Yes

When to Change	For more information, see “ _slow_start_initial Parameter ”.
Commitment Level	Unstable

`_slow_start_initial` Parameter

Description	Defines the maximum initial congestion window size in the maximum segment size (MSS) of a TCP connection. Refer to RFC 2414 on how the initial congestion window size is calculated.
Default	10
Range	1 to 10
Dynamic?	Yes
When to Change	Do not change the value. If the initial cwnd size causes network congestion under special circumstances, decrease the value.
Commitment Level	Unstable

`_time_wait_interval` Parameter

Description	Specifies the time in milliseconds that a TCP connection stays in TIME-WAIT state. For more information, refer to RFC 1122, 4.2.2.13.
Default	60,000 (60 seconds)
Range	1 second to 600,000 milliseconds
Dynamic?	Yes
When to Change	This parameter does not need to be changed in normal circumstances. If the normal usage of a system results in thousands and thousands of TCP connections waiting in TIME-WAIT state, the parameter value may be decreased. The value should not be lower than 10 seconds.

Commitment Level Unstable

`_tstamp_always` Parameter

Description	If set to 1, TCP always sends a SYN segment with the timestamp option. If set to 2, timestamps are completely disabled, regardless of whether the TCP connection was opened actively or passively. Note that if TCP receives a SYN segment with the timestamp option, TCP responds with a SYN segment with the timestamp option even if the parameter is set to 0.
Default	0 (disabled)
Range	0 (disabled), 1 (enabled), or 2 (disabled regardless of how TCP connection was opened)
Dynamic?	Yes
When to Change	If getting an accurate measurement of round-trip time (RTT) and TCP sequence number wraparound is a problem, enable this parameter. Refer to RFC 1323 for more reasons to enable this option.
Commitment Level	Unstable

`_wscale_always` Parameter

Description	When this parameter is enabled, which is the default setting, TCP always sends a SYN segment with the window scale option, even if the window scale option value is 0. Note that if TCP receives a SYN segment with the window scale option, even if the parameter is disabled, TCP responds with a SYN segment with the window scale option. In addition, the option value is set according to the receive window size. Refer to RFC 1323 for the window scale option.
Default	1 (enabled)
Range	0 (disabled) or 1 (enabled)
Dynamic?	Yes
When to Change	If there is an interoperability problem with an old TCP stack that does not support the window scale option, disable this parameter.

Commitment Level Unstable

cwnd-max Parameter

Description	Defines the maximum value of the TCP congestion window in bytes. For more information about the TCP congestion window, refer to RFC 1122 and RFC 2581.
Default	1,048,576
Range	128 to 1,073,741,824
Dynamic?	Yes
When to Change	This parameter does not need to be changed in normal circumstances. If the system needs to communicate with peers far away (round trip time in the order of hundreds of milliseconds) using very fast network (in the order of Gbps), increase the default value to match the bandwidth-delay product to those peers. Note that “ max-buf Parameter ” should also be increased at the same time.
Commitment Level	Stable

ecn Parameter

Description	Controls Explicit Congestion Notification (ECN) support. If this parameter is set to <code>never</code> TCP does not negotiate with a peer that supports the ECN mechanism. If this parameter is set to <code>passive</code> when initiating a connection, TCP does not tell a peer that it supports ECN mechanism. However, TCP tells a peer that it supports ECN mechanism when accepting a new incoming connection request if the peer indicates that it supports ECN mechanism in the SYN segment. If this parameter is set to <code>active</code> , in addition to negotiating with a peer on the ECN mechanism when accepting connections, TCP indicates in the outgoing SYN segment that it supports the ECN mechanism when TCP makes active outgoing connections. Refer to RFC 3168 for information about ECN.
-------------	---

Default	Active
Range	never, passive, or active
Dynamic?	Yes
When to Change	ECN can help TCP better handle congestion control. However, there might be existing TCP implementations, firewalls, NATs, and other non-conforming network devices that are confused by this mechanism. These devices do not comply to the IETF standard. It is suggested that these devices be replaced. In situations where replacing non-conforming devices is not feasible, this parameter value can be set to <i>passive</i> or <i>never</i> .
Commitment Level	Stable

largest-anon-port Parameter

Description	This parameter controls the largest port number TCP can select as an ephemeral port. An application can use an ephemeral port when it creates a connection with a specified protocol but not a port number. Ephemeral ports are not associated with a specific application. When the connection is closed, the port number can be reused by a different application.
Unit	Port number
Default	65,535
Range	32,768 to 65,535
Dynamic?	Yes
When to Change	When a larger ephemeral port range is required.
Commitment Level	Stable

max-buf Parameter

Description	Defines the maximum send and receive buffer size in bytes. This parameter controls how large the send and receive buffers are set to by an application that uses <code>setsockopt()</code> .
-------------	--

Default	1,048,576
Range	128,000 to 1,073,741,824
Dynamic?	Yes
When to Change	If TCP connections are being made in a high-speed network environment, increase the value to match the network link speed. The “cwnd-max Parameter” parameter should probably be increased at the same time.
Commitment Level	Stable

recv-buf Parameter

Description	Defines the default receive window size in bytes. Refer to “Per-Route Metrics” on page 181 for a discussion of setting a different value on a per-route basis. See also “max-buf Parameter” and “_recv_hiwat_minmss Parameter” .
Default	256,000
Range	2,048 to the current value of max-buf
Dynamic?	Yes
When to Change	An application can use <code>setsockopt (SO_RCVBUF)</code> to change the individual connection's receive buffer. See the <code>setsockopt(3C)</code> man page for information.
Commitment Level	Stable

sack Parameter

Description	If set to <code>active</code> , TCP always sends a SYN segment with the selective acknowledgment (SACK) permitted option. If TCP receives a SYN segment with a SACK-permitted option and this parameter is set to <code>passive</code> TCP responds with a SACK-permitted option. If the parameter is set to <code>never</code> TCP does not send a SACK-permitted option, regardless of whether the incoming segment contains the SACK permitted option.
-------------	---

	Refer to RFC 2018 for information about the SACK option.
Default	active
Range	never, passive, or active
Dynamic?	Yes
When to Change	SACK processing can improve TCP retransmission performance so it should be actively enabled. Sometimes, the other side can be confused with the SACK option actively enabled. If this confusion occurs, set the value to passive so that SACK processing is enabled only when incoming connections allow SACK processing.
Commitment Level	Stable

send-buf Parameter

Description	Defines the default send window size in bytes. Refer to “Per-Route Metrics” on page 181 for a discussion of setting a different value on a per-route basis. See also “max-buf Parameter” .
Default	49,152
Range	4,096 to the current value of “max-buf Parameter”
Dynamic?	Yes
When to Change	An application can use <code>setsockopt (SO_SNDBUF)</code> to change the individual connection's send buffer. See the <code>setsockopt(3C)</code> man page for information.
Commitment Level	Stable

smallest-anon-port Parameter

Description	This parameter controls the smallest port number TCP can select as an ephemeral port. An application can use an ephemeral port when it creates a connection with a specified protocol but not a port number. Ephemeral
-------------	--

ports are not associated with a specific application. When the connection is closed, the port number can be reused by a different application.

Unit	Port number
Default	32,768
Range	1,024 to 65,535
Dynamic?	Yes
When to Change	When a larger ephemeral port range is required.
Commitment Level	Stable

tcp_cwnd_normal Parameter

Description	<p>One of three variables for the congestion window burst throttle, along side <code>tcp_cwnd_infinite</code> and <code>tcp_cwnd_ss</code> that together manage packet transfers in cases of congestion.</p> <p>To prevent performance degradation from transfer congestion, change the parameter's value in a file in the <code>/etc/system.d</code> directory as follows:</p> <pre># echo "set ip:tcp_cwnd_normal=0xFF" >> /etc/system.d/site:filename # reboot</pre> <p>where <code>site:filename</code> refers to the file that contains the new parameter setting (<code>0xFF</code>). The new setting will be read from <code>/etc/system.d/file</code> into the <code>/etc/system</code> file during the reboot. The naming convention <code>site:filename</code> enables you to identify the file and the change that you implemented on the parameter. For more information about using files in <code>/etc/system.d</code>, see “/etc/system.d/ Directory Files” on page 18.</p> <p>For more information about the congestion window, refer to RFC 2581 and RFC 3390.</p>
Default	16
Range	1-65535
Dynamic?	Yes
When to Change	See Description

Commitment Level Unstable

TCP Parameters With Additional Cautions

Changing the following parameters is not recommended.

`_ip_abort_interval` Parameter

Description	<p>Specifies the default total retransmission timeout value for a TCP connection. For a given TCP connection, if TCP has been retransmitting for <code>_ip_abort_interval</code> period of time and it has not received any acknowledgment from the other endpoint during this period, TCP closes this connection.</p> <p>For TCP retransmission timeout (RTO) calculation, refer to RFC 1122, 4.2.3. See also “_rexmit_interval_max Parameter”.</p>
Default	5 minutes
Range	500 milliseconds to 1193 hours
Dynamic?	Yes
When to Change	Do not change this value. See <code>_rexmit_interval_max</code> for exceptions.
Commitment Level	Unstable

`_keepalive_interval` Parameter

Description	<p>This <code>ipadm</code> parameter sets a probe interval that is first sent out after a TCP connection is idle on a system-wide basis.</p> <p>Oracle Solaris supports the TCP keep-alive mechanism as described in RFC 1122. This mechanism is enabled by setting the <code>SO_KEEPALIVE</code> socket option on a TCP socket.</p> <p>If <code>SO_KEEPALIVE</code> is enabled for a socket, the first keep-alive probe is sent out after a TCP connection is idle for two hours, the default value of the <code>tcp_keepalive_interval</code> parameter. If the peer does not respond to the probe after eight minutes, the TCP connection is aborted. For more information, refer to “_rexmit_interval_initial Parameter”.</p>
-------------	---

You can also use the `TCP_KEEPALIVE_THRESHOLD` socket option on individual applications to override the default interval so that each application can have its own interval on each socket. The option value is an unsigned integer in milliseconds. Also see the [tcp\(4P\)](#) man page.

Default	2 hours
Range	10 seconds to 10 days
Units	Unsigned integer (milliseconds)
Dynamic?	Yes
When to Change	Do not change the value. Lowering it may cause unnecessary network traffic and might also increase the chance of premature termination of the connection because of a transient network problem.
Commitment Level	Unstable

`_recv_hiwat_minmss` Parameter

Description	Controls the default minimum receive window size. The minimum is <code>_recv_hiwat_minmss</code> times the size of maximum segment size (MSS) of a connection.
Default	8
Range	1 to 65,536
Dynamic?	Yes
When to Change	Do not change the value. If changing it is necessary, do not change the value lower than 4.
Commitment Level	Unstable

`_rexmit_interval_extra` Parameter

Description	Specifies a constant added to the calculated retransmission time out value (RTO).
-------------	---

Default	0 milliseconds
Range	0 to 7,200,000 milliseconds
Dynamic?	Yes
When to Change	Do not change the value. When the RTO calculation fails to obtain a good value for a connection, you can change this value to avoid unnecessary retransmissions.
Commitment Level	Unstable

`_rexmit_interval_initial` Parameter

Description	Specifies the default initial retransmission timeout (RTO) value for a TCP connection. Refer to “Per-Route Metrics” on page 181 for a discussion of setting a different value on a per-route basis.
Default	1,000 milliseconds
Range	1 millisecond to 20,000 milliseconds
Dynamic?	Yes
When to Change	Do not change this value. Lowering the value can result in unnecessary retransmissions. The <code>TCP_RTO_INITIAL</code> socket option can be used to change the initial retransmission timeout on a per-socket basis.
Commitment Level	Unstable

`_rexmit_interval_max` Parameter

Description	Defines the default maximum retransmission timeout value (RTO). The calculated RTO for all TCP connections cannot exceed this value. See also “<code>_ip_abort_interval</code> Parameter” .
Default	60,000 milliseconds
Range	1 millisecond to 7,200,000 milliseconds

Dynamic?	Yes
When to Change	Do not change the value in a normal network environment. If, in some special circumstances, the round-trip time (RTT) for a connection is about 10 seconds, you can increase this value. If you change this value, you should also change the <code>_ip_abort_interval</code> parameter. Change the value of <code>_ip_abort_interval</code> to at least four times the value of <code>_retransmit_interval_max</code> . The <code>TCP_RTO_MAX</code> socket option can be used to change the initial retransmission timeout on a per-socket basis.
Commitment Level	Unstable

`_retransmit_interval_min` Parameter

Description	Specifies the default minimum retransmission time out (RTO) value. The calculated RTO for all TCP connections cannot be lower than this value. See also “ _retransmit_interval_max Parameter ”.
Default	200 milliseconds
Range	1 millisecond to 7,200,000 milliseconds
Dynamic?	Yes
When to Change	Do not change the value in a normal network environment. TCP's RTO calculation should cope with most RTT fluctuations. If, in some very special circumstances, the round-trip time (RTT) for a connection is about 10 seconds, increase this value. If you change this value, you should change the <code>_retransmit_interval_max</code> parameter. Change the value of <code>_retransmit_interval_max</code> to at least eight times the value of <code>_retransmit_interval_min</code> . The <code>TCP_RTO_MIN</code> socket option can be used to change the initial retransmission timeout on a per-socket basis.
Commitment Level	Unstable

`_timestamp_if_wscale` Parameter

Description	If this parameter is set to 1, and the window scale option is enabled for a connection, TCP also enables the timestamp option for that connection.
-------------	--

Default	1 (enabled)
Range	0 (disabled) or 1 (enabled)
Dynamic?	Yes
When to Change	Do not change this value. In general, when TCP is used in high-speed network, protection against sequence number wraparound is essential. Thus, you need the timestamp option.
Commitment Level	Unstable

UDP Tunable Parameters

This section describes parameters specific to the UDP protocol.

`_ipv4_ttl` Parameter

Description	Controls the time to live (TTL) value in the IPv4 header for outbound UDP messages sent over IPv4. For more information, see the description for “ttl Parameter (IPv4)” .
Default	64 bytes
Range	1 to 255
Dynamic?	Yes
When to Change	Do not change this value in a normal network environment.
Commitment Level	Unstable

`_ipv6_hoplimit` Parameter

Description	Sets the value of the hop limit in the IPv6 header for the outbound UDP messages sent over IPv6. For more information, see the description for “hoplimit Parameter (IPv6)” .
-------------	--

Default	60
Range	1 to 255
Dynamic?	Yes
When to Change	Do not change this value in a normal network environment.
Commitment Level	Unstable

largest-anon-port Parameter

Description	This parameter controls the largest port number UDP can select as an ephemeral port. An application can use an ephemeral port when it creates a connection with a specified protocol but not a port number. Ephemeral ports are not associated with a specific application. When the connection is closed, the port number can be reused by a different application.
Unit	Port number
Default	65,535
Range	32,768 to 65,535
Dynamic?	Yes
When to Change	When a larger ephemeral port range is required.
Commitment Level	Stable

max-buf Parameter

Description	Defines the maximum send and receive buffer size for a UDP socket. It controls how large the send and receive buffers might be set to by an application that uses <code>setsockopt()</code> .
Default	2,097,152
Range	65,536 to 1,073,741,824

Dynamic?	Yes
When to Change	Increase the value of this parameter to match the network link speed if associations are being made in a high-speed network environment.
Commitment Level	Stable

recv-buf Parameter

Description	Defines the default receive buffer size for a UDP socket. For more information, see “max-buf Parameter” .
Default	57,344 bytes
Range	128 to the current value of max-buf
Dynamic?	Yes
When to Change	An application can use <code>setsockopt (SO_RCVBUF)</code> to change the individual connection's receive buffer. See the <code>setsockopt(3C)</code> man page for information.
Commitment Level	able

send-buf Parameter

Description	Defines the default send buffer size for a UDP socket. For more information, see “max-buf Parameter” .
Default	57,344 bytes
Range	1,024 to the current value of max-buf
Dynamic?	Yes
When to Change	An application can use <code>setsockopt (SO_SNDBUF)</code> to change the size for an individual socket. In general, you do not need to change the default value.
Commitment Level	Stable

smallest-anon-port Parameter

Description	This parameter controls the smallest port number UDP can select as an ephemeral port. An application can use an ephemeral port when it creates a connection with a specified protocol but not a port number. Ephemeral ports are not associated with a specific application. When the connection is closed, the port number can be reused by a different application.
Unit	Port number
Default	32,768
Range	1,024 to 65,535
Dynamic?	Yes
When to Change	When a larger ephemeral port range is required.
Commitment Level	Stable

SCTP Tunable Parameters

This section describes parameters related to the stream control transmission protocol.

_addip_enabled Parameter

Description	Enables or disables SCTP dynamic address reconfiguration.
Default	0 (disabled)
Range	0 (disabled) or 1 (enabled)
Dynamic?	Yes
When to Change	The parameter can be enabled if dynamic address reconfiguration is needed. Due to security implications, enable this parameter only for testing purposes.
Commitment Level	Unstable

`_cookie_life` Parameter

Description	Sets the lifespan of a cookie in milliseconds.
Default	60,000
Range	10 to 60,000,000
Dynamic?	Yes
When to Change	Generally, you do not need to change this value. This parameter might be changed in accordance with “ _rto_max Parameter”.
Commitment Level	Unstable

`_deferred_ack_interval` Parameter

Description	Sets the time-out value for SCTP delayed acknowledgment (ACK) timer in milliseconds.
Default	100 milliseconds
Range	1 to 60,000 milliseconds
Dynamic?	Yes
When to Change	Refer to RFC 2960, section 6.2.
Commitment Level	Unstable

`_heartbeat_interval` Parameter

Description	Computes the interval between HEARTBEAT chunks to an idle destination, that is allowed to heartbeat. An SCTP endpoint periodically sends an HEARTBEAT chunk to monitor the reachability of the idle destinations transport addresses of its peer.
Default	30 seconds

Range	0 to 86,400 seconds
Dynamic?	Yes
When to Change	Refer to RFC 2960, section 8.3.
Commitment Level	Unstable

`_ignore_path_mtu` Parameter

Description	Enables or disables path MTU discovery.
Default	0 (disabled)
Range	0 (disabled) or 1 (enabled)
Dynamic?	Yes
When to Change	Enable this parameter if you want to ignore MTU changes along the path. However, doing so might result in IP fragmentation if the path MTU decreases.
Commitment Level	Unstable

`_initial_mtu` Parameter

Description	Determines the initial maximum send size for an SCTP packet including the length of the IP header.
Default	1500 bytes
Range	68 to 65,535
Dynamic?	Yes
When to Change	Increase this parameter if the underlying link supports frame sizes that are greater than 1500 bytes.
Commitment Level	Unstable

`_initial_out_streams` Parameter

Description	Controls the maximum number of outbound streams permitted for an SCTP association.
Default	32
Range	1 to 65,535
Dynamic?	Yes
When to Change	Refer to RFC 2960, section 5.1.1.
Commitment Level	Unstable

`_initial_ssthresh` Parameter

Description	Sets the initial slow start threshold for a destination address of the peer.
Default	1,048,576
Range	1,024 to 4,294,967,295
Dynamic?	Yes
When to Change	Refer to RFC 2960, section 7.2.1.
Commitment Level	Unstable

`_ipv4_ttl` Parameter

Description	Controls the time to live (TTL) value in the IPv4 header for outbound SCTP messages sent over IPv4. For more information, see the description for “<code>ttl</code> Parameter (IPv4)” .
Default	64 bytes
Range	1 to 255
Dynamic?	Yes

When to Change	Do not change this value in a normal network environment.
Commitment Level	Unstable

_ipv6_hoplimit Parameter

Description	Sets the value of the hop limit in the IPv6 header for the outbound SCTP messages sent over IPv6. For more information, see the description for “hoplimit Parameter (IPv6)” .
Default	60
Range	1 to 255
Dynamic?	Yes
When to Change	Do not change this value in a normal network environment.
Commitment Level	Unstable

_maxburst Parameter

Description	Sets the limit on the number of segments to be sent in a burst.
Default	4
Range	2 to 8
Dynamic?	Yes
When to Change	You do not need to change this parameter. You might change it for testing purposes.
Commitment Level	Unstable

_max_in_streams Parameter

Description	Controls the maximum number of inbound streams permitted for an SCTP association.
-------------	---

Default	32
Range	1 to 65,535
Dynamic?	Yes
When to Change	Refer to RFC 2960, section 5.1.1.
Commitment Level	Unstable

_max_init_retr Parameter

Description	Controls the maximum number of attempts an SCTP endpoint should make at resending an INIT chunk. The SCTP endpoint can use the SCTP initiation structure to override this value.
Default	8
Range	0 to 128
Dynamic?	Yes
When to Change	The number of INIT retransmissions depend on “ _pa_max_retr Parameter ”. Ideally, <code>_max_init_retr</code> should be less than or equal to <code>_pa_max_retr</code> .
Commitment Level	Unstable

_new_secret_interval Parameter

Description	Determines when a new secret needs to be generated. The generated secret is used to compute the MAC for a cookie.
Default	2 minutes
Range	0 to 1,440 minutes
Dynamic?	Yes
When to Change	Refer to RFC 2960, section 5.1.3.

Commitment Level Unstable

`_pa_max_retr` Parameter

Description	Controls the maximum number of retransmissions (over all paths) for an SCTP association. The SCTP association is aborted when this number is exceeded.
Default	10
Range	1 to 128
Dynamic?	Yes
When to Change	The maximum number of retransmissions over all paths depend on the number of paths and the maximum number of retransmission over each path. Ideally, <code>sctp_pa_max_retr</code> should be set to the sum of “ _pp_max_retr Parameter ” over all available paths. For example, if there are 3 paths to the destination and the maximum number of retransmissions over each of the 3 paths is 5, then <code>_pa_max_retr</code> should be set to less than or equal to 15. (See the Note in Section 8.2, RFC 2960.)
Commitment Level	Unstable

`_pp_max_retr` Parameter

Description	Controls the maximum number of retransmissions over a specific path. When this number is exceeded for a path, the path (destination) is considered unreachable.
Default	5
Range	1 to 128
Dynamic?	Yes
When to Change	Do not change this value to less than 5.
Commitment Level	Unstable

`_prscptp_enabled` Parameter

Description	Enables or disables the partial reliability extension (RFC 3758) to SCTP.
Default	1 (enabled)
Range	0 (disabled) or 1 (enabled)
Dynamic?	Yes
When to Change	Disable this parameter if partial reliability is not supported in your SCTP environment.
Commitment Level	Unstable

`_rto_initial` Parameter

Description	Controls the initial retransmission timeout (RTO) in milliseconds for all the destination addresses of the peer.
Default	3,000
Range	1,000 to 60,000,000
Dynamic?	Yes
When to Change	Refer to RFC 2960, section 6.3.1.
Commitment Level	Unstable

`_rto_max` Parameter

Description	Controls the upper bound for the retransmission timeout (RTO) in milliseconds for all the destination addresses of the peer.
Default	60,000
Range	1,000 to 60,000,000
Dynamic?	Yes

When to Change	Refer to RFC 2960, section 6.3.1.
Commitment Level	Unstable

`_rto_min` Parameter

Description	Sets the lower bound for the retransmission timeout (RTO) in milliseconds for all the destination addresses of the peer.
Default	1,000
Range	500 to 60,000
Dynamic?	Yes
When to Change	Refer to RFC 2960, section 6.3.1.
Commitment Level	Unstable

`_shutack_wait_bound` Parameter

Description	Controls the maximum time, in milliseconds, to wait for a SHUTDOWN ACK after having sent a SHUTDOWN chunk.
Default	60,000
Range	0 to 300,000
Dynamic?	Yes
When to Change	Generally, you do not need to change this value. This parameter might be changed in accordance with “ _rto_max Parameter ”.
Commitment Level	Unstable

`_xmit_lowat` Parameter

Description	Controls the lower limit on the send window size.
-------------	---

Default	8,192
Range	8,192 to 1,073,741,824
Dynamic?	Yes
When to Change	Generally, you do not need to change this value. This parameter sets the minimum size required in the send buffer for the socket to be marked writable.
Commitment Level	Unstable

cwnd-max Parameter

Description	Controls the maximum value of the congestion window for an SCTP association.
Default	1,048,576
Range	128 to 1,073,741,824
Dynamic?	Yes
When to Change	This parameter does not need to be changed in normal circumstances. If the system needs to communicate with peers far away (round trip time in the order of hundreds of milliseconds) using very fast network (in the order of Gbps), increase the default value to match the bandwidth-delay product to those peers. Note that <code>max-buf</code> parameter should also be increased at the same time.
Commitment Level	Stable

largest_anon_port Parameter

Description	This parameter controls the largest port number SCTP can select as an ephemeral port. An application can use an ephemeral port when it creates a connection with a specified protocol but not a port number. Ephemeral ports are not associated with a specific application. When the connection is closed, the port number can be reused by a different application.
-------------	---

Unit	Port number
Default	65,535
Range	32,768 to 65,535
Dynamic?	Yes
When to Change	When a larger ephemeral port range is required.
Commitment Level	Stable

max-buf Parameter

Description	Controls the maximum send and receive buffer size in bytes. It controls how large the send and receive buffers might be set to by an application that uses <code>setsockopt()</code> .
Default	1,048,576
Range	102,400 to 1,073,741,824
Dynamic?	Yes
When to Change	Increase the value of this parameter to match the network link speed if associations are being made in a high-speed network environment.
Commitment Level	able

recv-buf Parameter

Description	Defines the default receive buffer size in bytes. See also “max-buf Parameter” .
Default	102,400
Range	8,192 to the current value of max-buf
Dynamic?	Yes

When to Change	An application can use <code>setsockopt (SO_RCVBUF)</code> to change the individual connection's receive buffer. See the setsockopt(3C) man page for information.
Commitment Level	able

send-buf Parameter

Description	Defines the default send buffer size in bytes. See also " max-buf Parameter ".
Default	102,400
Range	8,192 to the current value of <code>max-buf</code>
Dynamic?	Yes
When to Change	An application can use <code>setsockopt (SO_SNDBUF)</code> to change the individual connection's send buffer.
Commitment Level	Stable

smallest-anon-port Parameter

Description	This parameter controls the smallest port number SCTP can select as an ephemeral port. An application can use an ephemeral port when it creates a connection with a specified protocol but not a port number. Ephemeral ports are not associated with a specific application. When the connection is closed, the port number can be reused by a different application.
Unit	Port number
Default	32,768
Range	1,024 to 65,535
Dynamic?	Yes
When to Change	When a larger ephemeral port range is required.

Commitment Level table

ICMP Tunable Parameters

This section describes parameters related to the Internet control message protocol.

`_ipv4_ttl` Parameter

Description	Controls the time to live (TTL) value in the IPv4 header for outbound ICMP request and error report messages sent over IPv4. For more information, see the description for “ttl Parameter (IPv4)” .
Default	64 bytes
Range	1 to 255
Dynamic?	Yes
When to Change	Do not change this value in a normal network environment.
Commitment Level	Unstable

`_ipv6_hoplimit` Parameter

Description	Sets the value of the hop limit in the IPv6 header for the outbound ICMP request and error report messages sent over IPv6. For more information, see the description for “hoplimit Parameter (IPv6)” .
Default	60
Range	1 to 255
Dynamic?	Yes
When to Change	Do not change this value in a normal network environment.
Commitment Level	Unstable

Per-Route Metrics

You can use per-route metrics to associate some properties with IPv4 and IPv6 routing table entries.

For example, a system has two different network interfaces, a fast Ethernet interface and a gigabit Ethernet interface. The system default `recv_maxbuf` is 128,000 bytes. This default is sufficient for the fast Ethernet interface, but may not be sufficient for the gigabit Ethernet interface.

Instead of increasing the system's default for `recv_maxbuf`, you can associate a different default TCP receive window size to the gigabit Ethernet interface routing entry. By making this association, all TCP connections going through the route will have the increased receive window size.

For example, the following is in the routing table (`netstat -rn`), assuming IPv4:

```
Routing Table: IPv4
Destination      Gateway          Flags   Ref     Use    Interface
-----
192.0.2.0/27     192.0.2.4/27    U       1       4     net0
192.0.2.32/27    192.0.2.36/27  U       1       4     net1
default          192.0.2.1/27    UG      1       8
```

In this example, do the following:

```
# route change -net 192.0.2.32/27 -recvpipe x
```

Then, all connections going to the `192.0.2.32/27` network, which is on the `net1` link, use the receive buffer size `buff-size`, instead of the default `128,000` receive window size.

If the destination is in the `a.b.c.d` network, and no specific routing entry exists for that network, you can add a prefix route to that network and change the metric. For example:

```
# route add -net a.b.c.d 192.0.2.1/27 -netmask a.b.c.d-netmask
# route change -net a.b.c.d -recvpipe buff-size
```

Note that the prefix route's gateway is the default router. Then, all connections going to that network use the receive buffer size `y`. If you have more than one interface, use the `-ifp` argument to specify which interface to use. This way, you can control which interface to use for specific destinations. To verify the metric, use the `route get` command.

System Facility Parameters

This chapter describes most of the parameters default values for various system facilities.

For other types of tunable parameters, refer to the following:

- Oracle Solaris kernel tunable parameters – [Chapter 2, “Oracle Solaris Kernel Tunable Parameters”](#)
- Oracle Solaris ZFS tunable parameters – [Chapter 3, “Oracle Solaris ZFS Tunable Parameters”](#)
- NFS tunable parameters – [Chapter 4, “NFS Tunable Parameters”](#)
- Internet Protocol Suite tunable parameters – [Chapter 5, “Internet Protocol Suite Tunable Parameters”](#)

System Default Parameters

The functioning of various system facilities is governed by a set of values that are read by each facility on startup. The values for each facility might be stored in a file for the facility located in the `/etc/default` directory, or in properties of a service instance in the Service Management Facility (SMF) configuration repository. For more information about SMF services and properties, see [Managing System Services in Oracle Solaris 11.4](#).

For information about setting power management properties, see [Managing System Information, Processes, and Performance in Oracle Solaris 11.4](#).

autofs Property

You can display or configure SMF `autofs` properties by using the `sharectl` command. For example:

```
# sharectl get autofs
timeout=600
```

```
automount_verbose=false
automountd_verbose=false
nobrowse=false
trace=0
environment=
# sharectl set -p timeout=200 autofs
```

For details, see the [sharectl\(8\)](#) man page.

cron Facility

This facility enables you to disable or enable cron logging.

devfsadm File

This file is not currently used.

fs File

File system administrative commands have a generic and file system-specific portion. If the file system type is not explicitly specified with the `-F` option, a default is applied. The value is specified in this file. For more information, see the Description section of the [default_fs\(5\)](#) man page.

ftp Facility

This facility enables you to set the `ls` command behavior to the RFC 959 `NLST` command. The default `ls` behavior is the same as in the previous Oracle Solaris release.

For details, see the [ftp\(1\)](#) man page.

inetinit Facility

This facility enables you to configure TCP sequence numbers and to enable or disable support for 6to4 relay routers.

init Service

System initialization properties are now part of the following SMF service:

```
svc:/system/environment:init
```

You can display and configure system initialization properties, such as TZ and LANG, by using similar syntax:

```
# svccfg -s svc:/system/environment:init
svc:/system/environment:init> setprop
Usage: setprop pg/name = [type:] value
setprop pg/name = [type:] ([value...])
```

Set the pg/name property of the currently selected entity. Values may be enclosed in double-quotes. Value lists may span multiple lines.

```
svc:/system/environment:init> listprop
umask                                application
umask/umask                          astring      022
umask/value_authorization            astring      solaris.smf.value.environment
environment                          application
environment/LANG                    astring
environment/LC_ALL                  astring
.
.
.
```

For more information, see the FILES section of the [init\(8\)](#) man page.

ipsec Facility

This facility enables you to configure network security parameters, such as IKE daemon debugging information.

kbd Configuration Properties

Keyboard configuration properties are now part of the following SMF service:

```
svc:/system/keymap:default
```

You display and configure keyboard properties by using similar syntax:

```
# svccfg -s svc:/system/keymap:default
svc:/system/keymap:default> setprop
Usage: setprop pg/name = [type:] value
setprop pg/name = [type:] ([value...])
```

Set the pg/name property of the currently selected entity. Values may be enclosed in double-quotes. Value lists may span multiple lines.

```
svc:/system/keymap:default> listprop
general                               framework
general/complete                      astring
general/enabled                       boolean    false
keymap                                 system
keymap/console_beeper_freq            integer    900
keymap/kbd_beeper_freq                integer    2000
keymap/keyboard_abort                 astring    enable
keymap/keyclick                       boolean    false
.
.
.
```

For more information, see the [kbd\(1\)](#) man page.

keyserv Facility

For details, see the `/etc/default/keyserv` information in the FILES section of the [keyserv\(8\)](#) man page.

login Facility

For details, see the `/etc/default/login` information in the FILES section of the [login\(1\)](#) man page.

mpathd Facility

This facility enables you to set `in.mpathd` configuration parameters.

For details, see the [in.mpathd\(8\)](#) man page.

nfs Properties

You can display or configure SMF NFS properties by using the `sharectl` command. For example:

```
# sharectl get nfs
servers=1024
lockd_listen_backlog=32
lockd_servers=1024
lockd_retransmit_timeout=5
grace_period=90
server_versmin=2
server_versmax=4
client_versmin=2
client_versmax=4
server_delegation=on
nfsmapid_domain=
# sharectl set -p grace_period=60 nfs
```

For details, see the [nfs\(5\)](#) man page.

nfslogd Log File

For details, see the Description section of the [nfslogd\(8\)](#) man page.

nss Facility

This facility enables you to configure `initgroups()` lookup parameters.

For details, see the [nss\(5\)](#) man page.

passwd Facility

For details, see the `/etc/default/passwd` information in the FILES section of the [passwd\(1\)](#) man page.

su Facility

For details, see the `/etc/default/su` information in the FILES section of the [su\(8\)](#) man page.

syslog Facility

For details, see the `/etc/default/syslogd` information in the FILES section of the [syslogd\(8\)](#) man page.

tar Facility

For a description of the `-f` function modifier, see the [tar\(1\)](#) man page.

If the `TAPE` environment variable is not present and the value of one of the arguments is a number and `-f` is not specified, the number matching the `archiveN` string is looked up in the `/etc/default/tar` file. The value of the `archiveN` string is used as the output device with the blocking and size specifications from the file.

For example:

```
% tar -c 2 /tmp/*
```

This command writes the output to the device specified as `archive2` in the `/etc/default/tar` file.

telnetd Facility (Deprecated)

This file identifies the default `BANNER` that is displayed upon a telnet connection.

utmpd Daemon

The `utmpd` daemon monitors `/var/adm/utmpx` (and `/var/adm/utmp` in earlier Oracle Solaris versions) to ensure that `utmp` entries inserted by non-root processes by `pututxline()` are cleaned up on process termination.

Two entries in `/etc/default/utmpd` are supported:

- `SCAN_PERIOD` – The number of seconds that `utmpd` sleeps between checks of `/proc` to see if monitored processes are still alive. The default is 300.
- `MAX_FDS` – The maximum number of processes that `utmpd` attempts to monitor. The default value is 4096 and should never need to be changed.

◆◆◆ A P P E N D I X A

System Check Script

Confirming Flush Behavior on the System

This script facilitates confirmation that flush behavior is correct on your system after tuning ZFS and flash storage. For more details, refer to [“Ensuring Proper Cache Flush Behavior for Flash and NVRAM Storage Devices” on page 93](#). After you have completed the steps indicated, run the following script.

```
#!/bin/ksh
#
#cd /dev/rdisk
#for d in *d0; do
# /export/home/admin1/bin/sdflush.sh $d
#done
#
#

if [[ $# -ne 1 ]]; then
    echo "Usage: $0 cctx..."
    exit 1;
fi

sd=`iostat -x $1 2>&1 | grep sd | nawk '{print $1}' | sed s/sd//`
printf "Value for %s : " $1
echo '*sd_state::softstate 0t'$sd' | ::print struct sd_lun un_phy_blocksize' \
    | mdb --kernel

#echo '*sd_state::softstate 0t'$sd' | ::print struct sd_lun un_f_suppress_cache_flush' \
#echo '*sd_state::softstate 0t'$sd' | ::print struct sd_lun un_phy_blocksize' \
```


Index

A

_addip_enabled, 168
_addrs_per_if, 134
arp-publish-count, 145
arp-publish-interval, 145
_arp_defend_interval, 140
_arp_defend_period, 140
_arp_defend_rate, 141
_arp_fastprobe_count, 142
_arp_fastprobe_interval, 142
_arp_probe_count, 142
_arp_probe_interval, 143
autofs, 183
autoup, 31

C

_conn_req_max_q, 147
_conn_req_max_q0, 148
_conn_req_min, 148
_cookie_life, 169
cron, 184
cwnd-max (TCP), 156
cwnd-max (SCTP), 177

D

dax_stats_flags, 54
ddi_msix_alloc_limit parameter, 55
default_stksize, 26
default_tsb_size, 79
_defend_interval, 143

_deferred_ack_interval, 149, 169
_deferred_acks_max, 149
desfree, 41
dnlc_dir_enable, 68
dnlc_dir_max_size, 68
dnlc_dir_min_size, 69
dnlc_dircache_percent, 69
doiflush, 32
dopageflush, 32
_dup_recovery, 144

E

ecn, 156
enable_tsb_rss_sizing, 80

F

fastscan, 42
_forwarding_src_routed, 135
fs, 184
fsflush, 33
ftp, 184

H

handspreadpages, 43
_heartbeat_interval, 169
hires_tick, 78
hoplimit (IPv6), 137
hostmodel, 137

I

- _icmp_err_burst, 135
- _icmp_err_interval, 135
- _icmp_return_data_bytes, 146
- _ignore_path_mtu, 170
- inetinit, 184
- init, 185
- _initial_mtu, 170
- _initial_out_streams, 171
- _initial_ssthresh, 171
- intr_force, 59
- intr_throttling, 60
- _ip_abort_interval, 161
- ip_queue_fanout, 58
- ip_queue_worker_wait, 57
- ipcl_conn_hash_size, 58
- ipsec, 185
- _ipv4_ttl (ICMP), 180
- _ipv4_ttl (TCP), 150
- _ipv4_ttl (UDP), 165
- _ipv4_ttl SCTP, 171
- _ipv6_hoplimit (ICMP), 180
- _ipv6_hoplimit (SCTP), 172
- _ipv6_hoplimit (TCP), 150
- _ipv6_hoplimit (UDP), 165

K

- kbd, 185
- _keepalive_interval, 161
- keyserv, 186
- kmem_flags, 52
- kmem_stackinfo, 53

L

- largest-anon-port (SCTP), 177
- largest-anon-port (TCP), 157
- largest-anon-port (UDP), 166
- lgrp_mem_pset_aware, 82
- _local_dack_interval, 151

- _local_dacks_max, 151
- _local_slow_start_initial, 152
- logevent_max_q_sz, 27
- login, 186
- lotsfree, 43
- lpg_alloc_prefer, 83
- lwp_default_stksize, 27

M

- max-buf (SCTP), 178
- max-buf (TCP), 157
- max-buf (UDP), 166
- _max_defend, 144
- _max_in_streams, 172
- _max_init_retr, 173
- max_nprocs, 35
- _max_temp_defend, 144
- _maxburst, 172
- maxpgio, 44
- maxphys, 65
- maxpid, 38
- maxuprc, 35
- maxusers, 36
- min_percent_cpu, 45
- minfree, 46
- moddebug, 56
- mpathd, 186
- mr_enable, 60

N

- nccsize, 70
- ndp-unsolicit-count, 145
- ndp-unsolicit-interval, 145
- _ndp_defend_interval, 140
- _ndp_defend_period, 140
- _ndp_defend_rate, 141
- _new_secret_interval, 173
- nfs:nacache, 120
- nfs:nfs3_async_clusters, 100

nfs:nfs3_bsize, 102
nfs:nfs3_cots_timeo, 105
nfs:nfs3_do_symlink_cache, 108
nfs:nfs3_dynamic, 110
nfs:nfs3_jukebox_delay, 110
nfs:nfs3_lookup_neg_cache, 112
nfs:nfs3_max_threads, 115
nfs:nfs3_max_transfer_size, 116
nfs:nfs3_max_transfer_size_clts, 118
nfs:nfs3_max_transfer_size_cots, 119
nfs:nfs3_nra, 121
nfs:nfs3_pathconf_disable_cache, 124
nfs:nfs3_shrinkreaddir, 125
nfs:nfs4_async_clusters, 101
nfs:nfs4_bsize, 103
nfs:nfs4_cots_timeo, 105
nfs:nfs4_do_symlink_cache, 108
nfs:nfs4_lookup_neg_cache, 113
nfs:nfs4_max_threads, 116
nfs:nfs4_max_transfer_size, 117
nfs:nfs4_nra, 122
nfs:nfs_allow_preepoch_time, 98
nfs:nfs_async_clusters, 99
nfs:nfs_async_timeout, 102
nfs:nfs_cots_timeo, 104
nfs:nfs_disable_rddir_cache, 106
nfs:nfs_do_symlink_cache, 107
nfs:nfs_dynamic, 109
nfs:nfs_lookup_neg_cache, 111
nfs:nfs_nra, 120
nfs:nfs_shrinkreaddir, 125
nfs:nfs_write_error_interval, 126
nfs:nfs_write_error_to_cons_only, 127
nfs:nrnode, 123
nfs_max_threads, 114
nfslogd, 187
nfsrv:rfs_write_async, 128
ngroups_max, 37
noexec_user_stack, 29
nss, 187
nstrpush, 75

P

_pa_max_retr, 174
pageout_reserve, 47
pages_before_pager, 48
pages_pp_maximum, 48
passwd, 187
_pathmtu_interval, 146
physmem, 30
pidmax, 38
_policy_mask, 136
_pp_max_retr, 174
_prscpt_enabled, 175
pt_cnt, 73
pt_max_pty, 74
pt_pctofmem, 75

R

recordsize
 ZFS file system property, 95
recv-buf (SCTP), 178
recv-buf (TCP), 158
recv-buf (UDP), 167
recv-multicast-scaling, 138
_recv_hiwat_minmss, 162
reserved_procs, 39
_respond_to_echo_broadcast, 136
_respond_to_echo_multicast, 136
_rev_src_routes, 152
_rexmit_interval_extra, 162
_rexmit_interval_initial, 163
_rexmit_interval_max, 163
_rexmit_interval_min, 164
rlim_fd_cur, 65
rlim_fd_max, 66
rlim_fd_sys, 67
rpcmod:clnt_idle_timeout, 130
rpcmod:clnt_max_conns, 129
rpcmod:svc_idle_timeout, 130
_rst_sent_rate, 152
_rst_sent_rate_enabled, 153

_rto_max, 175
_rto_max, 175
_rto_min, 176
rx_copy_threshold, 61
rx_limit_per_intr, 61
rx_queue_number, 62
rx_ring_size, 62

S

sack, 158
send-buf (SCTP), 179
send-buf (TCP), 159
send-buf (UDP), 167
send-redirects, 139
_shutack_wait_bound, 176
_slow_start_after_idle, 153
_slow_start_initial, 154
slowscan, 49
smallest-anon-port (SCTP), 179
smallest-anon-port (TCP), 160
smallest-anon-port (UDP), 168
strmsgsz, 76, 77
su, 188
syslog, 188

T

tar, 188
tcp_cwnd_normal, 160
throttlefree, 50
_time_wait_interval, 154
timer_max, 78
tmpfs_maxkmem, 71
tmpfs_minfree, 72
tsb_alloc_hiwater, 80
tsb_rss_factor, 81
_tstamp_always, 155
_tstamp_if_wscale, 164
ttl (IPv4), 139
tune_t_fsflushr, 34

tune_t_minarmem, 51
tx_copy_threshold, 63
tx_queue_number, 63
tx_ring_size, 64

U

utmpd, 188

W

_wscale_always, 155

X

_xmit_lowat, 176

Z

ZFS file system property
 recordsize, 95
zfs_arc_max, 88
zfs_arc_min, 87
zfs_prefetch_disable, 89