

Millionaire Certificate User Guide

Oracle FLEXCUBE Universal Banking

Release 12.0.2.0.0

Part No. E49740-01

September 2013

Millionaire Certificate User Guide
September 2013
Oracle Financial Services Software Limited

Oracle Park

Off Western Express Highway
Goregaon (East)
Mumbai, Maharashtra 400 063
India

Worldwide Inquiries:

Phone: +91 22 6718 3000

Fax:+91 22 6718 3001

www.oracle.com/financialservices/

Copyright © 2007, 2013, Oracle and/or its affiliates. All rights reserved.

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate failsafe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

This software or hardware and documentation may provide access to or information on content, products and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Contents

1. Preface	1-1
1.1 Introduction	1-1
1.2 Audience	1-1
1.3 Documentation Accessibility	1-1
1.4 Organization	1-1
1.5 Glossary of Icons	1-2
1.6 Related Documents	1-2
2. Overview - Millionaire Certificates	2-1
2.1 Introduction	2-1
2.2 Millionaire Certificate	2-1
2.3 Lien Millionaire Certificates	2-2
2.4 Draw Procedure	2-2
2.5 Scope of the Module	2-2
2.6 MB Module Functions & Features	2-3
2.6.1 Flexible Parameters Definition	2-3
2.6.2 MC/LMC Customers	2-3
2.6.3 Instrument Numbering	2-3
3. Maintenances	3-1
3.1 Introduction	3-1
3.1.1 Maintaining Pay-in Parameter Details	3-1
3.1.2 Viewing Pay-in Parameter Details Summary	3-2
3.1.3 Maintaining Monthly Provision Details	3-3
3.1.4 Viewing Monthly Provision Details Summary	3-4
3.1.5 Maintaining Draw Parameter Details	3-5
3.1.6 Viewing Draw Parameter Summary	3-6
3.1.7 Processing EOD Batch	3-7
4. Defining Product Attributes	4-1
4.1 Introduction	4-1
4.1.1 Capturing Millionaire Certificate Product Details	4-1
4.1.2 Specifying Preferences for a Product	4-3
4.1.3 Specifying Charges (ICCF) for a Product	4-4
4.1.4 Viewing Product Definition Details Summary	4-5
5. Processing MB Contract	5-1
5.1 Introduction	5-1
5.2 Capturing Millionaire Certificate Contract Details	5-1
5.2.1 Denomination Details	5-4
5.2.2 Customer Details	5-4
5.2.3 Certificate Details	5-6
5.2.4 Viewing Millionaire Certificate Contract Summary	5-7
5.2.5 Querying Customer Balance	5-8
5.2.6 Mapping Customer Reference to CIF	5-9
6. Payment	6-1
6.1 Introduction	6-1

6.1.1	<i>Millionaire Certificate Payment Details</i>	6-1
7.	Accounting Entries and Advices	7-1
7.1	Introduction	7-1
7.2	MB Events	7-1
7.3	Accounting Entries	7-1
7.3.1	<i>MC Issuance – Cash/Cheque/Credit Card/Account transfer</i>	7-2
7.3.2	<i>MC Re-issuance</i>	7-2
7.3.3	<i>MC Issuance to winners</i>	7-2
7.3.4	<i>MC Liquidation/Encashment</i>	7-2
7.3.5	<i>MC Monthly Provisioning</i>	7-3
7.3.6	<i>MC Reversal</i>	7-3
7.3.7	<i>LMC Issuance</i>	7-3
7.3.8	<i>LMC Manual Roll-over</i>	7-3
7.3.9	<i>LMC Cancellation</i>	7-3
7.3.10	<i>LMC Monthly Amortization</i>	7-4
7.3.11	<i>LMC Reversal</i>	7-4
7.4	Advices	7-4
7.5	Notification:.....	7-5
8.	Function ID Glossary	8-1

1.1 Introduction

Millionaire Certificate (MC) is a savings and investment opportunity which offers a maximum returns of 1000 times the investment value and at the same time the customer's certificates are completely capital guaranteed and en-cashable at any point in time.

Oracle FLEXCUBE Millionaire Certificate module (MB) module helps you to facilitate MC/LMC transactions. This module provide features to issue, redeem, partially redeem, cancel and mark as lost or reissue certificates. Certificates can be bought by cash or cheque or credit card. Certificates can also be bought on lien by paying the interest amount.

1.2 Audience

This manual is intended for the following User/User Roles:

Role	Function
Back Office Trade Finance Department Clerks	Contract Input functions except Authorization.
Back Office Trade Finance Department Officers	Contract Authorization, maintenance of static data specific to this module.
Front end Trade Finance Product Managers	Product definition functions excluding authorization. Query functions.
End of Day Operators	End and beginning of day related processing functions
Bank's Financial Controller/Trade Finance Department Manager	Branch level processing related setup for this module and Authorization of the same.
MIS Department Officers	Query/Report functions.

1.3 Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

1.4 Organization





This Manual is organized into the following chapters:

Chapter 1	<i>About this Manual</i> gives information on the intended audience. It also lists the various chapters covered in this User Manual.
------------------	--

Chapter 2	<i>Overview - Millionaire Certificates</i> gives you an overview of the MB module of Oracle FLEXCUBE.
Chapter 3	<i>Maintenances</i> chapter elaborates on the required maintenance for enabling and using the Millionaire Certificates (MB) module of Oracle FLEXCUBE.
Chapter 4	<i>Defining Product Attributes</i> explains about defining the basic information such as associated accounting roles, events, branches/customers restrictions, charges, product preferences, MIS & UDF and so on specific to setting up MB product.
Chapter 5	<i>Processing MB Contract</i> details about Capturing and processing Contract details related to MB
Chapter 6	<i>Payment</i> elaborates upon the operations which can be performed using the function present as part of the Millionaire Certificate (MB) module of Oracle FLEXCUBE.
Chapter 7	<i>Accounting Entries and Advices</i> list the suggested accounting roles and events related to the MB module of Oracle FLEXCUBE.
Chapter 8	<i>Function ID Glossary</i> has alphabetical listing of Function/Screen ID's used in the module with page references for quick navigation.

1.5 Glossary of Icons

This User Manual may refer to all or some of the following icons.

Icons	Function
	Exit
	Add row
	Delete row
	Option List

1.6 Related Documents

You may need to refer to any or all of the User Manuals while working on the MB module:

- Core Entities
- Inventory
- ELCM
- Procedures
- Products
- User Defined Fields

2. Overview - Millionaire Certificates

2.1 Introduction

This chapter gives you an overview of the Millionaire Certificate (MC) module of Oracle FLEXCUBE. There are two types of certificates issued by the bank:

- Millionaire Certificate (MC)
- Lien Millionaire Certificates (LMC)

2.2 Millionaire Certificate

Millionaire Certificate (MC) is a savings and investment opportunity which offers a good returns on your investment and certificates are completely capital guaranteed and encashable at any point of time. The subscription to MC is in multiple of thousands only.

To subscribe to MC, you should hold a Valid Visa (Transit/ Visit/Business/Residential) and a Passport. MC can be bought from any of the branches of the bank or through any channels like their associated exchanges and gets processed from the bank. The non-residential clients would be able to redeem it through a Power of Attorney issued with proper documentation.

Customers of the bank can get certificates attached to their account if the MCs have been purchased under the CIF # of the account as well. Non customers of the bank can purchase the MC and later associates with the Customer or CIF if he becomes customer and declares the same to the bank.

Inventory module is used to track the movement of the instruments between central vault and branches and tracks the status of each instrument by serial number.

The MB module provides you with the following features:

- MC is open ended and don't have any maturity date and can be withdrawn at any point in time across the counter. But any encashment within X number of days from the date of purchase shall be subject to a nominal pre-encashment fee of 2.5% of total certificate value.
- Certificates are Non-Interest bearing, non-negotiable and non-pledge able to any third party. Customers can walk into any Bank branch and en-cash their certificates. Withdrawal of MC can be cash or transfer to customer account with the bank.
- Minimum investment allowed as certificates is issued in respective LCY equivalents.
- One time fee is charged per transaction irrespective of number of certificates issued.
- Draw is conducted on a daily/weekly/bimonthly/monthly/quarterly basis with minimum savings condition.
- Secured over draft facility is there to meet the immediate financial needs while remaining in the running for a million dirham draw. You can avail the facility of a secured over draft against their Millionaire certificates – up to 90% of MM value at the rate of 8.5%
- MC can be purchased on-line by account holders of your bank and non-account holders. All credit card holders are accepted to purchase MC (customers & non customers). For other bank credit card customers, there is an additional MC issuance charge of 1.5% on the (transaction amount + normal issuance fee).
- In case of lost certificates, the bank reprints the MC and may charge a new issuance fee.

- After winning the draw, MM certificates equivalent to the winning amount would be issued to the winner without any cash payments. Winner has an option to redeem the certificates.

2.3 Lien Millionaire Certificates

Lien Millionaire Certificates (LMC) is another product offered by the bank. All features are like the Millionaire Certificates but for the below mentioned features:

- While purchasing the MC you have an option to pay the interest (Currently 6% per year per certificate) and get add-on notional MC. Notional certificates are eligible to participate in the draw.
- The number of MC you can buy on lien is dependent on the number of MC you hold.
- The subscription transaction fee (MC) is waived-off if the customer opts for the Lien.
- Liated MC can be renewed every year by paying the same interest. If the renewal is not done then the notional certificate will be active up to grace period end defined at product preference and after grace period end Notional certificate is dropped automatically.
- The bank has an option to Reverse the MC/LMC with an option to refund the interest when:
 - Reversal of MC contract is allowed only if it has not undergone liquidation/re-issuance and it should not be linked to any LMC contracts.
 - Reversal of LMC contract is allowed only if it has not undergone cancellation/rollover/reissuance/monthly interest amortization.
- If a customer liquidates the MC, then proportionate of LMC should be dropped accordingly as per eligibility matrix. Interest rate charged is not refundable and unearned interest is transferred to earned GL.

2.4 Draw Procedure

A member from the Economic Panel would be part of the draw. This is generally conducted in a Mall or a Beach or an open place where public gathering generally happens. The Lottery happens through a throw of dice corresponding to the Units place, hundreds place etc... considering the total number of reference active deposits in consideration.

Currently the Bank is getting the sequence/reference no. through the lot and then contacting the customer support centre to ensure that the deposit is active. Oracle FLEXCUBE provides the reference number and the corresponding certificate number immediately instead of using the manual process.

2.5 Scope of the Module

The MB module comprises the following high-level functions:

- Product Definition
- Contract Input
- Pay-in Parameter Maintenance
- Monthly Provision Maintenance
- Draw Parameter Maintenance
- 'Factory shipped' report is only for a single report for draw data.
- 'Advices' is only to provide advice field tags.

2.6 MB Module Functions & Features

The following sections give you a brief overview of the MB module's various functions and features.

2.6.1 Flexible Parameters Definition

Parameters Definition for millionaire certificate product, associated charges, accounting entries and preferences are completely user defined and flexible.

Certificate issuance, encashment, cancellation (including partial cancellation) and re-issuance are handled as different stages/events of a contract.

Inventory module is used to track the flow of inventory from head office to various branches. It also tracks the status of the instrument.

MC contracts can be used as collateral to a liability in the collateral maintenance screen, in the ELCM module. MC contract is then blocked to the extent of collateralized amount.

2.6.2 MC/LMC Customers

All customers of MC/LMC (including customers/credit card holders of your bank and walk-in customers/credit card holders) are CIF in Oracle FLEXCUBE. Each type of MC customers are created with different charge groups to facilitate differential charging, if any.

For new walk-in customers, during MC issuance you can record the basic details of the customer in 'Customer details' section of MC contract issuance screen. These details are stored against the customer reference number and would not create a CIF in the system. The system generated customer reference number would then be mapped against the standard walk-in CIF defined in the branch parameters.

Upon fresh/first time purchase of MC by CIF, system dynamically generates the customer reference number and associates it to the CIF. This reference number would be a ten digit number - branch code followed by running sequence number.

System would not validate the MC customers based on customer nationality/visa details/age.

2.6.3 Instrument Numbering

MC/LMC would involve the following two numbers:

- Certificate number – a ten digit number with branch code followed by running sequence number.
- Control/key/serial number - unique number printed on the stationary/instrument and would be used to authenticate the issued certificates.

3.1 Introduction

As part of enabling and using the Millionaire Certificates (MB) module of Oracle FLEXCUBE, there are several maintenances to be performed. These maintenances have been elaborated upon in the sections given below.

Note

Unless specified otherwise, all maintenances specified below allow all standard maintenance functions – Add, Modify, Delete, Authorize, Close, Re-open, and Inquiry. The maintenance functions also log all maintenances in the Audit Trail.

The common maintenance related to Millionaire Certificate transactions are maintained in the following screens:

- Function ID 'CSDDEMAN' under the heading 'Maintaining Currency Denomination Details' in CS module
- Function ID 'IVDSTKCD' under the heading 'Stock Catalog Definition' in Instruments Inventory Tracking (IV) module.
- Function ID 'IVDTXNAS' under the heading 'Adjust Inventory Balance' in Instruments Inventory Tracking (IV) module.

3.1.1 Maintaining Pay-in Parameter Details

You can maintain the general ledger code for each product, branch and pay-in-option (viz. by cash, cheque and credit card) in the 'Pay-in parameter Maintenance' screen from the head office level.

To invoke the 'Pay-in parameter Maintenance' screen, enter 'MBDMPAY' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

◆ Pay-In Parameter Maintenance

New Enter Query

Product Code * Product Description
Branch Code * General Ledger Code *
Pay In * Cash

Maker Date Time:
Checker Date Time:
Mod No Record Status
Authorization Status

Exit

You can maintain the following details here.

Product Code

Specify the MC product code for which you are maintaining the details.

The description for the specified product gets displayed in the adjacent field.

Branch Code

Specify the branch code where the product MC product is issued.

Pay-in Option

Select a valid paying option from the drop-down list. The values are:

- Cash
- Cheque
- Credit card.

General ledger code

Specify the GL code for the selected pay-in option.

MC issuance through cheque and credit card is a deposit in teller module to the specified GL codes. MC issuance through cash would impact the till in teller module and update the specified cash GL. During MC issuance, based on the pay-in option, these GL codes would be used for further processing.

3.1.2 Viewing Pay-in Parameter Details Summary

You can view the summary of monthly provision details through the 'Pay-in Parameter Summary' screen.

To invoke the 'Pay-in Parameter Summary' screen, enter 'MBSMBPAY' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

The screenshot shows the 'Pay-In Parameter Summary' application window. The window has a title bar with 'Pay-In Parameter Summary' and standard window controls. Below the title bar, there is a search area with 'Advanced Search' and 'Reset' buttons. The main area contains several input fields: 'Authorization Status' (dropdown), 'Record Status' (dropdown), 'Product Code' (text with a search icon), and 'Branch Code' (text with a search icon). There is also a 'Pay In' dropdown field. Below these fields is a table with columns: 'Authorization Status', 'Record Status', 'Product Code', 'Branch Code', and 'Pay In'. The table is currently empty. At the bottom right of the window is an 'Exit' button.

You can query the contract records with the following details

- Authorization Status
- Record Status
- Product Code
- Branch Code

- Pay in

Click 'search' button to view the records with the specified values.

3.1.3 **Maintaining Monthly Provision Details**

You can maintain monthly provision for MC / LMC in the 'Monthly Provision Maintenance' screen from the head office level.

For a product, provision is allowed only once in a calendar month and if it is done for 'ALL' products, then provisioning for individual products is not allowed. Similarly, If provisioning is done for specific product then system would not allow provisioning for 'ALL' products in the given calendar month.

To invoke the 'Monthly Provision Maintenance' screen, enter 'MBDMPROV' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

The screenshot shows a software window titled "Monthly Provision Maintenance". At the top left, there are buttons for "New" and "Enter Query". The main area contains a form with the following fields:

- Product Code * (with a red asterisk)
- Provision Currency
- Provision Amount * (with a red asterisk)
- Product Description
- Provision Date

At the bottom of the window, there are several fields for user and system information:

- Maker
- Checker
- Mod No
- Date Time:
- Record Status
- Authorization Status

An "Exit" button is located in the bottom right corner of the window.

You can maintain the following details here.

Product Code

Select a valid MC/LMC product code for provisioning from the list of values maintained. You can specify 'ALL' products also for provisioning.

The description for the specified product gets displayed in the adjacent field. Provision date gets defaulted as the system date.

Provision Amount

Specify the amount for provision. The currency gets displayed in the adjacent field.

After the provision is authorized you cannot modify the record. System compute the branch provision share for all the branches holding active MC/LMC as on provision date and post provision accounting entries for all these branches.

Branch provision amount is computed by apportioning the 'Provision amount', based on the number of MC/LMC in books of branch under consideration with that of total number of MC/

LMC in books of all branches. System would use contract originating branch as the basis to group MC/LMC for a given branch.

Branch Provision Share = (Provision amount * Total MC/LMC in books of branch "A" / Total MC/LMC Deposits in all branches).

Upon computing branch provision amount, system would trigger the 'PROV' event to pass the inter-branch accounting entries as mentioned below:

In Books of Branch "A":

Debit– Expense GL<Branch Provision Share>

Credit – Head Office Account in books of branch "A" <Branch Provision Share>

In Books of Head Office:

Debit – Branch "A" Account in Head Office books <Branch Provision Share>

Credit – MM Provision GL (Liability GL) <Branch Provision Share>

The date of provision gets defaulted.

3.1.4 Viewing Monthly Provision Details Summary

You can view the summary of monthly provision details through the 'Monthly Provision - Summary' screen.

To invoke the 'Monthly Provision - Summary' screen, enter 'MBSMPROV' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

The screenshot shows a web-based application window titled "Monthly Provision". At the top, there are "Advanced Search" and "Reset" options. Below this, there are several search criteria: "Authorization Status" (a dropdown menu), "Record Status" (a dropdown menu), "Product Code" (a text input field with a search icon), "Provision Date" (a date input field with a search icon), "Provision Currency" (a text input field with a search icon), and "Provision Amount" (a text input field with a search icon). Below the search fields, there is a "Records per page" dropdown set to "15" and a "1 Of 1" indicator. The main area of the window is a table with the following columns: "Authorization Status", "Record Status", "Product Code", "Provision Date", "Provision Currency", and "Provision Amount". The table currently displays one record, which is mostly blank. At the bottom right of the window, there is an "Exit" button.

You can query the contract records with the following details

- Authorization Status
- Record Status
- Product Code
- Provision Date
- Provision Currency

- Provision Amount

Click 'search' button to view the records with the specified values.

3.1.5 **Maintaining Draw Parameter Details**

You can maintain the data file extraction details in the 'Draw parameter Maintenance' screen from the head office level.

To invoke the 'Draw parameter Maintenance' screen, enter 'MBDDRMNT' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

You can maintain the following details here.

A unique draw reference number gets displayed here.

Cut-off date

Specify the cut-off date for the draw. All active certificates with value date lesser than the specified cut-off date are eligible to participate in the draw.

Min. No. of MC

Specify the Minimum number of MC. If the number of MC held by the customer (including all mapped to customer reference number) is less than this specified quantity then the customer is not eligible to participate in the draw.

Product Restrictions

Indicate the restriction for the product during the draw. You can select one of the following options:

- Disallowed
- Allowed

Product

You can specify the list of MC/LMC products to be included in the restriction for the draw.

Product Code

Specify the product to be included in the restriction for the draw. The product description gets displayed.

Branch Restrictions

Indicate the restriction for the branch during the draw. You can select one of the following options:

- Disallowed
- Allowed

Branch

You can specify the list of branch to be included in the restriction for the draw. System would use contract originating branch as the basis to tag MC/LMC to a given branch.

Branch Code

Specify the branch to be included in the restriction for the draw. The branch description gets displayed.

Certificate Restrictions

Indicate the restriction for the certificate numbers during the draw. You can select one of the following options:

- Disallowed
- Allowed

Exclude Certificate Number

You can specify the list of certificate numbers to be included in the restriction for the draw.

Certificate No

Specify the certificate number to be included in the restriction for the draw.

After the authorization, system would extract the eligible certificate details based on the data provided.

Note

Only active MC/LMC will be considered for the draw. All certificates that have been re-deemed or cancelled will not be eligible for the draw.

An OBIEE report gets displayed with draw data based on this maintenance. Report accepts 'Draw reference number' as the input parameter and displays sequence number, certificate number and customer reference number for all certificates eligible for the draw.

3.1.6 Viewing Draw Parameter Summary

You can view the summary of monthly provision details through the 'Draw Parameter Summary' screen.

To invoke the Monthly Provision - Summary' screen, enter 'MBSDRMNT' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

The screenshot shows a web application window titled 'Summary'. At the top, there are 'Advanced Search' and 'Reset' buttons. Below this, there are several search filters: 'Authorization Status' (a dropdown menu), 'Record Status' (a dropdown menu), 'Draw Reference Number' (a text input field with a search icon), and 'Min No of MC' (a text input field with a search icon). To the right, there is a 'Cutoff Date' (a date picker). Below the filters, there is a 'Records per page' dropdown set to '15' and a '1 Of 1' indicator. The main area contains a table with columns: 'Authorization Status', 'Record Status', 'Draw Reference Number', 'Cutoff Date', 'Min No of MC', 'Product Restriction', and 'Bra'. The table is currently empty. At the bottom right of the window, there is an 'Exit' button.

You can query the contract records with the following details

- Authorization Status
- Record Status
- Draw Reference Number
- Cutoff Date
- Min No of MC

Click 'search' button to view the records with the specified values.

3.1.7 Processing EOD Batch

During the End of Transaction Input, to amortize the interest received in advance on LMC, an EOD batch (MBBEODFN) is run on a monthly basis. The lien amount is amortized over the period of one year based on the following formula.

Monthly amortization amount = Total interest amount/(No of Days in Year – No Of days passed by) * No. of days in a month.

In the month when LMC is issued, the no. of days for the above calculations is from date of issuance till month end and in the last month i.e. 12th month, the total unamortized amount would be amortized.

System triggers the 'LMCA' event to post accounting entries for monthly amortization amount.

On the maturity date of LMC, this EOD batch marks the LMC status as 'Pending renewal'. LMC with 'Pending Renewal' status are not eligible to participate in the draw. If the LMC contract is not renewed before the grace period then this EOD batch would 'Close' the LMC contract.

4. Defining Product Attributes

4.1 Introduction

In this chapter, we shall discuss the manner in which you can define attributes specific to a MB Product.

In the product definition, you can specify basic information, associated accounting roles, events, branches/customers restrictions, charges, product preferences, MIS & UDF. Separate products are created for millionaire certificate and lien millionaire certificate.

4.1.1 Capturing Millionaire Certificate Product Details

You can maintain the MB product definition in the 'Millionaire Certificate Product Definition' screen. To invoke the screen, type 'MBDPRMNT' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

The screenshot shows a software window titled "Millionaire Certificate Product Definition". The window has a menu bar with "New" and "Enter Query" options. The main content area contains the following fields and controls:

- Product Code: [Text Input]
- Product Description: [Text Input]
- Product Type: Millionaire Certificate, Lien Millionaire Certificate
- Start Date: [Text Input]
- End Date: [Text Input]
- Remarks: [Text Input]

Below the main area is a navigation bar with links: Accounting Role | Events | Branch & Currency | Customer | MIS | Preferences | Charges. At the bottom, there is a footer section with the following fields and controls:

- Maker: [Text Input]
- Checker: [Text Input]
- Mod No: [Text Input]
- Date Time: [Text Input]
- Date Time: [Text Input]
- Record Status: [Text Input]
- Authorization Status: [Text Input]
- Exit: [Button]

You can specify all attributes related to MB product here.

The buttons on this screen are explained below:

Buttons	Description
Accounting Roles	Click this button to define the accounting role to accounting head mapping.
Events	Click this button to select the events for the product and then maintain event-wise accounting entries and advices.
Branch	Click this button to maintain the list of allowed/ disallowed branches for the product.

Customer	Click this button to maintain the list of allowed/ disallowed customers/customer categories.
Preferences	Click this button to define preferences of the product.
Charges	Click this button to define charge components, rules, events and other associated details.
Fields	Click this button to provide values for the UDFs associated with the screen.

For any product you create in Oracle FLEXCUBE, you can define generic attributes, such as branch, currency, and customer restrictions, interest details, tax details, etc., by clicking on the appropriate icon in the horizontal array of icons in this screen.

Product Code

Specify the code you assign to a product which is used to identify the product throughout the module. The code should contain four characters. You can follow your own convention for devising the code; but at least one of the characters should be a letter of the English alphabet.

Since the code that you define is used to identify the product, it should be unique across the modules of Oracle FLEXCUBE. For instance, if you have assigned the code 'MC01' to a particular product in this module, you cannot use it as a code in any other module.

Description

Specify a brief description of the product, which will be associated with the product for information retrieval purposes.

Product Type

Indicate the type of product from the options given below:

- Millionaire Certificate
- Lien Millionaire Certificate

Start/End Date

A product can be set up for use over a specific period, by defining a start and an end date. The Issue Date of an MC involving a product should be:

- The same as or later than the Start Date.
- The same as or earlier than the End Date.

The start and end dates of a product come in handy when you are defining a product for a scheme, which is open for a specific period.

Remarks

You can enter information about the product, intended for the internal reference of your bank. The remarks are displayed when the details of the MC are displayed or printed, but not printed on any correspondence with the customer.

4.1.2 Specifying Preferences for a Product

Click 'Preference' button from 'Millionaire Certificate Product Definition' screen to invoke the preference screen.

The screenshot shows a 'Preferences' window with the following fields and tables:

- Product Code
- Product Description
- Stock Code *
- KYC Limit *
- Renewal Grace Period
- Product Currency *
- Certificate Value *
- Certificate Number Mask *

Two tables are displayed:

MC Start Number *	MC End Number *	LMC Eligibility Ra

LMC Start Number *	LMC End Number *	Issuance Price

Buttons: Ok, Exit

You can specify the following values here:

Product code and the description for the code get displayed here.

Stock Code

Specify the stock code of pre-printed MC stationary/inventory. It should be a valid code in inventory module.

Certificate Value displays the value of the associated MC product. The denomination value associated with the selected stock code would be defaulted.

Renewal Grace Period

Specify the grace period for LMC renewal/manual rollover. Grace period would be specified as number of calendar days.

You can renew the LMC only after the maturity date.

If the LMC contract is not renewed before the grace period then EOD batch would 'Close' the LMC contract.

If LMC contract is renewed (Event: ROLL) before the grace period then system would increase the maturity value of the contract by a year.

LMC contracts in grace period, which are yet to be renewed, are not eligible to participate in the draw.

Certificate Number Mask

Specify the mask for certificate numbers.

Typical 'Certificate Number Mask' would be 'bbbnnnnnnn', where 'bbb' would represent the branch code and 'n' would represent the numeric character.

Product currency

Specify the currency associated with the product/certificate value/issuance price for LMC. Currency code should be the LCY code.

KYC Verification Limit

Specify the limit for KYC verification. After the MC issuance to customers, if the cumulative value of MC held by the customer (including the current contract and by considering all the mapped customer reference number) exceeds this limit then system validates the KYC compliance of the CIF.

LMC Eligibility Ratio

Specify the following details to calculate LMC eligibility ratio for a given range of MC held by the customers.

Based on the number of MC held by the customers, system computes the maximum number of LMC that can be held by the customer. Any decimal/fractional output will be truncated in deriving the maximum eligible LMC.

LMC Price

Specify the following details to maintain the issuance price for a given range of LMC issued to the customers.

4.1.3 Specifying Charges (ICCF) for a Product

Click 'Charge' button on 'Millionaire Certificate Product Definition' screen to define the charge components, rules, events and other associated details.

The screenshot shows the 'Charge Details' window with the following sections and fields:

- Product Code** and **Product Description** (text boxes)
- Component Details** (1 Of 1):
 - Component *** (text box)
 - Description** (text box)
 - Charge Type** (dropdown)
 - Third Party Type** (text box)
 - Net Consideration
 - Advice Charge
 - Stop Association
 - Propagation Required
 - Default From Class** (button)
 - Debit/Credit** (dropdown)
 - Add/Subtract** (dropdown)
 - SWIFT Qualifier** (text box)
- Event Details**:
 - Event For Association** (text box)
 - Description** (text box)
 - Event For Liquidation** (text box)
 - Description** (text box)
 - Event For Application** (text box)
 - Description** (text box)
 - Basis Amount Tag** (text box)
 - Description** (text box)
- Rule Details**:
 - Settlement Currency** (text box)
 - Rule** (text box)
 - Description** (text box)
 - Default Waiver
 - Capitalize
 - Collect LC Advising Charges in Bills
- Other Details**:
 - Allow Rule Amendment
 - Amend After Association
 - Allow Amount Amendment
 - Accrual Required
 - Amend After Application
 - Consider as Discount
 - Discount Basis** (dropdown)

Buttons: **Ok** and **Exit**

Issuance charge is a flat amount based charge associated to appropriate events. It could also be a percentage of total amounts of certificates issued.

Pre-encashment charge is a 'tenor basis' charge with 2.5% charge for 0-90 days and 0% thereafter. The tenor of the open-ended MC contract (with maturity date as null) would be computed as (Application date – Value date).

Charge currency code should be the LCY code.

Note

Any changes in product parameters would be applied for prospective contracts/events only.

For further information on the generic attributes that you can define for a product, please refer the following Oracle FLEXCUBE User Manuals under Modularity:

- *Product Definition*
- *User Defined Fields*
- *Settlements*

Millionaire Certificate Product Definition' screen allows all standard maintenance functions – Add, Modify, Delete, Authorize, Close, Re-open, and Inquiry. It also log all maintenances in the Audit Trail.

4.1.4 **Viewing Product Definition Details Summary**

You can view the summary of monthly provision details through the 'Product Definition Summary' screen.

To invoke the 'Product Definition Summary' screen, enter 'MBSPRMNT' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

The screenshot shows a web application window titled "Summary". At the top, there is a search bar with "Advanced Search" and "Reset" buttons. Below the search bar, there are four search criteria: "Authorization Status" (dropdown menu), "Record Status" (dropdown menu), "Product Code" (text input field with a search icon), and "Product Type" (text input field with a search icon). Below the search criteria, there is a table with the following columns: "Authorization Status", "Record Status", "Product Code", "Product Type", "KYC Limit", "Certificate Value", "Stock Code", and "Product Name". The table is currently empty. At the bottom right of the window, there is an "Exit" button.

You can query the contract records with the following details

- Authorization Status
- Record Status
- Product code
- Product Type

Click 'search' button to view the records with the specified values.

5. Processing MB Contract

5.1 Introduction

An MC/LMC contract is an instruction wherein a customer requests the bank to issue a Millionaire Certificate. Certificate issuance, encashment, lost, partial re-issue, cancellation and re-issuance are handled as different stages or events of a contract.

5.2 Capturing Millionaire Certificate Contract Details

You can input MC/LMC contract in the 'Millionaire Certificate Contract Input' screen.

For walk-in customers, during MC issuance you can record the basic details of the customer in 'Customer details' section of MC contract issuance screen. These details are stored against the customer reference number without creating a CIF in the system. The system generated customer reference number is then be mapped against the standard walk-in CIF defined in the branch parameters.

To invoke the 'Millionaire Certificate Contract Input' screen, enter 'MBDTRONL' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

The screenshot shows the 'Millionaire Certificate Contract Input' application window. It contains several input fields organized into two main sections: 'Contract Details' and 'Other Details'. The 'Contract Details' section includes fields for Product Code, Transaction Type (set to 'Normal Issue'), No of Certificates, Charge Group, Product Description, Customer No, and Pay-In Option (set to 'Cash'). The 'Other Details' section includes fields for Contract Reference, User Reference, Currency, Value Date, Certificate Amount, Customer Reference, Control Number, Source Code (set to 'FLEXCUBE'), Source Reference, Issuance Price, Book Date, Maturity Date, Account No/ GL Code, Original Purchase Date, and Remarks. At the bottom of the window, there is a navigation bar with tabs for 'Certificate Details', 'Denomination Details', 'Customer Details', 'Events', 'Charges', 'MIS', and 'Fields'. Below the navigation bar, there are fields for 'Maker', 'Date Time', 'Status', 'Checker', 'Date Time', and 'Authorization Status', along with an 'Exit' button.

The system generated contract reference number gets displayed in the screen. You can specify the following details here.

Product Code

Specify the millionaire certificate product to be used in the contract. The product description gets displayed in the adjacent field.

Customer No

Specify the CIF number of the customer. Customer Reference Number mapped to the selected customer gets displayed.

For new walk-in customers, you have to select the standard walk-in-customer id as maintained in the branch parameters. Additional details of new walk-in-customers should be recorded in the customer details section.

Transaction Type

Specify the type of transaction from the drop-down options. Transaction types are associated to a specific event for differential charging and accounting. The options are:

- Normal Issue (Event : INIT) For normal issuance of MC to customers.
- Replacement Issue (Event : RIMC) In case of lost certificates, an indemnity may be taken from customer and the bank reprints the MC certificates with new system generated certificate numbers. Old control number would be marked as lost and system would force the user to enter new control number.

Note

This option is available only on contract amendment.

- Issue to winners (Event : WIMC) - For issuance of MC to winners. "Pay-in option" has to be "Other GL" – enabling user to specify the debit GL (eg. HO account in CPC books or MM provision GL or other expense GL).
- Lien Issue (Event : INIT) For issue of notional/lien MC.
- Lien Rollover (Event : ROLL) For renewing the lien.

Note

This option would be available only on contract amendment.

User Reference

Specify the user reference number.

Source Code

Specify the source of the contract.

Source Reference

Specify the source reference of the contract.

Value Date

Specify the value date of the contract. Only MC issuance can be back dated. Future dated contract is not supported.

The application date gets displayed as the booking date of the contract.

For LMC issuance, maturity date is computed as (value date + one year). Upon rollover of LMC, maturity date gets incremented by a year.

Note

For MC contract maturity date would be blank/null

No of Certificates

Specify the number of certificates participating in the specified transaction type.

The MC certificate value or LMC issuance price gets displayed as Issuance Price.

While saving, the issuance price for MC/LMC is defaulted by the system. LMC issuance price is derived based on the number of liened certificates requested in the contract and LMC pricing maintained in product definition.

Control Number

Specify the control number of pre-printed stationary/instrument which should be a valid stock number as maintained through 'Adjust Inventory Balance' - 'MC - Branch to User'.

For contracts initiated from FCDB source, system would not allow to track control number.

The computed contract value based on the number of certificates and issuance price gets displayed in the Amount.

Pay-in option

Select the pay option from the drop-down list. The options are:

- Cash - cash GL of the current branch gets impacted.
- Cheque
- Account transfer - system allows only LCY accounts to be selected.
- Credit card
- Other GL.

Account No/GL code

Specify the GL code from which the contract value should be debited. If the GL code is not selected then while saving system would default the relevant GL code from pay-in parameter maintenance.

- For pay-in-option as account transfer, specify the customer account number (linked to the selected CIF). System would support only LCY accounts.
- For pay-in-option as 'Other GL', specify the GL code from which the contract value should be debited. This option is allowed only if the 'Transaction Type' is selected as 'Issue to Winners'.

The original purchase purchase/issue date of the certificates gets displayed.

Remarks

Specify any additional remarks or information for the contract.

Charge Group

While selecting the CIF, system defaults the associated charge group. You can modify the charge group of the contract.

5.2.1 Denomination Details

For cash payment, you can maintain denomination details. You should operationally maintain appropriate denomination details for the amount settled across counter, which system does not validate.

Denomination Code	Denomination Value	Units	Total Amount

Currency Total Amount

Denomination Code

Specify the denomination code for the currency.

Denomination Value

Specify the value of the denomination.

Units

Specify the units of the denomination.

Currency and the total amount get displayed here.

5.2.2 Customer Details

For new walk-in customers, during MC issuance you can record the basic details of the customer in this section. These details are stored against the customer reference number and

would not create a CIF in the system. The system generated customer reference number should then be mapped against the standard walk-in CIF defined in the branch parameters.

The screenshot shows a 'Customer Details' window with the following fields and sections:

- Customer Name:** Customer Name (text), Party Type (dropdown, set to 'Individual')
- Customer Short Name:** Customer Short Name (text), Branch (text)
- Address For Correspondence:** Address 1, Address 2, Address 3, Address 4 (text)
- Geographic:** Country Code (text), Nationality (text), Language (text)
- Unique Identifier:** Name (text), Value (text), KYC Status (dropdown, set to 'Yet To Verify'), Charge Group (text)
- Passport Details:** Passport Number (text), Issue Date (text), Expiry Date (text)

Buttons: Ok, Exit

You can maintain the following details of a walk-in customer here. Branch code gets displayed.

Customer Name

Specify the customer name.

Customer Short Name

Specify a short name for the customer.

Party type

Select the party type of the customer from the following drop-down options:

- Individual
- Corporate
- Bank

Address for Correspondence

You can provide the customer address in the following fields:

- Address 1
- Address 2
- Address 3
- Address 4

Geographic

You can provide the geographic information of the customer here.

Country Code

Specify the country code of the customer.

Nationality

Specify the nationality of the customer.

Language

Specify the language of the customer for communication.

Unique Identifier

You can provide the unique identifier details of the customer here.

Name

Specify the name of the unique identifier details of the customer.

Value

Specify the value of the identifier details of the customer.

KYC Status

Select the status of KYC checking of the customer from the following drop-down options:

- Yet to Verify
- Verified

Charge Group

Specify the charge group of the customer.

Passport Details

You can provide the passport details of the customer here.

Passport Number

Specify the passport number of the customer.


Issue Date

Specify the issue date of the customer passport.

Expiry Date

Specify the expiry date of the customer passport.

5.2.3 Certificate Details



The screenshot shows a window titled "Certificate Details" with a table containing the following columns: Control Number, Certificate Start no, Certificate End No, No of Certificates, and Certificate Amount. The table is currently empty. The window also features a "Go" button and "Ok" and "Exit" buttons at the bottom.

When you save the contract and system performs the following:

- Upon MC issuance to customers, if the cumulative value of MC held by the customer (including the current contract and by considering all the mapped customer reference number) exceeds the KYC limit then system would validate the KYC compliance of the CIF. If the CIF is not KYC compliant then system raises an error.

- Contracts initiated from FCDB source can only be viewed in the system. Customer can do further lifecycle in FCDB only. System would not allow any operations/processing on FCDB contracts through Oracle FLEXCUBE source.
- You can operate contracts initiated through other branches. For account transfer, system would post accounting entry to the branch in which the account is held.
- Reversal of MC contracts is allowed only if it has not undergone liquidation/reissuance and it should not be linked to any LMC contracts.
- Reversal of LMC contracts is allowed only if it has not undergone cancellation/rollover/reissuance/monthly interest amortization. In such reversals the accounting entries are reversed to refund the interest collected.
- During the reversal of MC contract, REVR entry gets fired and it reverses the INIT accounting entry.

5.2.4 Viewing Millionaire Certificate Contract Summary

You can view the summary of millionaire certificate contracts through the 'Millionaire Certificate Contract Summary' screen.

To invoke the 'Millionaire Certificate Contract Summary' screen, enter 'MBSTRONL' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

The screenshot shows a web application window titled 'Summary'. At the top, there are 'Advanced Search' and 'Reset' buttons. Below this, there are two columns of search filters, each with a text input field and a search icon:

- Contract Reference
- Currency
- Source Code
- Auth Status
- Product Code
- Contract Status
- Source Reference

Below the filters, there is a 'Records per page' dropdown set to '15' and a '1 Of 1' indicator. The main area contains a table with the following columns: Contract Reference, Product Code, Currency, Contract Status, Source Code, Source Reference, and Auth Status. The table is currently empty. At the bottom right of the window, there is an 'Exit' button.

You can query the contract records with the following details

- Contract Reference
- Product Code
- Currency
- Contract Status
- Source Code
- Source Reference
- Authorization Status

Click 'search' button to view the records with the specified values.

5.2.5 Querying Customer Balance

You can query the MC and LMC holding balance of a customer in the 'Customer Balance Inquiry' screen.

To invoke the 'Customer Balance Inquiry' screen, enter 'MBDCUBAL' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

The screenshot shows the 'Customer Balance Inquiry' application window. At the top, there are two buttons: 'New' and 'Enter Query'. Below these are input fields for 'Customer No *', 'Control No', 'Customer Reference No' (with 'ALL' selected), and 'Certificate No'. A 'Query' button is positioned below the 'Control No' field. The main area is titled 'Balance Details' and features a table with columns: 'Customer Reference No', 'Product Code', 'Contract Reference', 'Control No', and 'Certificate Start No'. Below the table, there are two summary fields: 'No of MC Held' and 'No of LMC Held'. An 'Exit' button is located in the bottom right corner of the window.

System would display the MC/LMC holding details of the given customer number and customer reference number.

Customer No

Specify the customer number/CIF to query the balance of that customer.

Customer Reference Number

Specify a valid reference number mapped to the selected customer number. You can select 'ALL' to view the consolidated holdings of the customer (across all customer reference number mapped to the CIF).

Control No

Specify the control number to query the balance.

Certificate Number

Specify the MC certificate number of the customer to query the balance.

Click 'Query' button to view the balance details as per the selected criteria. You can view the following details:

- Customer Reference No
- Record Code
- Contract Reference No
- Control No
- Certificate Start No
- Certificate End No
- Quantity
- Total Certificate Value

- Status

Number of MC held and Number of LMC held by the customer gets displayed.

5.2.6 Mapping Customer Reference to CIF

You can map a single or multiple customer reference number to a CIF with one of the customer reference number to be selected as default. Customer reference mapping can be done through 'Customer Reference Mapping' screen.

To invoke the 'Customer Balance Inquiry' screen, enter 'MBDCMAP' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

The screenshot shows the 'Customer Reference Mapping' application window. At the top, there is a title bar with a diamond icon and the text 'Customer Reference Mapping'. Below the title bar, there are two buttons: 'New' and 'Enter Query'. A text input field labeled 'Customer No *' is positioned below these buttons. The main area of the window is titled 'Customer Reference Details' and contains a table with one row. The table has two columns: 'Customer Reference No *' and 'Default'. The first row in the table has a checkbox in the first column and the text 'Default' in the second column. Below the table, there is a 'Go' button and navigation arrows. At the bottom of the window, there are several fields: 'Maker', 'Checker', 'Mod No', 'Date Time', 'Record Status', and 'Authorization Status'. An 'Exit' button is located in the bottom right corner.

You can map customer reference number or multiple customer reference numbers to a CIF with one of the customer reference number to be selected as default here.

Customer No

Select the customer number or CIF for mapping the customer reference number.

Customer Reference Details

Customer Reference No

Select the customer reference number to map the selected customer number/CIF. The customer reference numbers which are yet to be mapped to a customer number are listed in the LOV.

You cannot map a customer reference number already mapped to one CIF to other CIF.

Default

Specify the default customer reference number of the selected customer. One of the mapped customer reference numbers has to be selected as the default reference number for the CIF.

6.1 Introduction

This chapter elaborates upon the operations which can be performed using the function present as part of the Millionaire Certificate (MB) module of Oracle FLEXCUBE. These operations have been elaborated upon in the sections given below.

6.1.1 Millionaire Certificate Payment Details

You can liquidate or cancel the Millionaire Certificates or Lien Millionaire Certificates using the 'Millionaire Certificate Payment Input' screen. System allows you to perform partial liquidation for MC contracts also using the same screen.

To invoke the 'Millionaire Certificate Payment Input' screen, enter 'MBDTRPAY' in the field at the top right corner of the Application Toolbar and then click the adjoining arrow button.

The screenshot shows the 'Millionaire Certificate Payment Input' application window. It features a menu bar with 'New' and 'Enter Query' options. Below the menu bar, there are fields for 'Version' and 'Number' with a 'Of' separator. The main area is divided into two sections: 'Contract Details' and 'Other Details'. The 'Contract Details' section includes fields for 'Product Code *', 'Transaction Type *' (set to 'Liquidate'), 'Product Description', 'Customer No *', 'Active Certificates *', 'Contract Reference *', 'No of Certificate to Liquidate', and 'Pay-In Option *' (set to 'Cash'). The 'Other Details' section includes fields for 'User Reference *', 'Currency *', 'Value Date *', 'Customer Reference', 'Control Number', 'Liquidated Certificate Amount', 'Charge Group', 'Source Code * FLEXCUBE', 'Source Reference *', 'Issuance Price *', 'Book Date', 'Maturity Date', 'Account No/ GL Code *', and 'LMC Control No'. At the bottom, there is a navigation bar with tabs for 'Certificate Details', 'Denomination Details', 'Charges', and 'Fields'. Below the navigation bar, there are fields for 'Maker', 'Date Time', 'Status', 'Checker', 'Date Time', and 'Authorization Status', along with an 'Exit' button.

The following details are displayed here:

- Product Code
- Product Description
- Customer No
- Customer Reference Number
- Transaction Type as liquidate

Contract Reference No

Specify the contract reference number.

User Reference

Specify the user reference number.

Source Code

Specify the source of the contract.

Source Reference

Specify the source reference of the contract.

The following details are displayed:

- Value Date - system defaults the application date to value date.
- Book Date - book date of the contract
- Maturity Date - maturity date of the contract.
- Issuance Price - MC certificate value or LMC issuance price.

No of Certificates

Specify the number of certificates participating in the specified transaction type.

The computed contract value based on the number of certificates and issuance price gets displayed as amount.

Control Number

Specify the control number of pre-printed stationary/instrument which should be a valid stock number as maintained through 'Adjust Inventory Balance' - 'MC - Branch to User'.

System would accept this control number value only for partial liquidation of MC contract. The details of remaining active MC are printed on the instrument with the specified control number.

In case of complete liquidation of MC contract or cancellation of LMC contract, control number value has to be left blank/null.

For contracts initiated from FCDB source, system would not allow to track control number.

LMC Control Number

Specify the control number of pre-printed stationary/instrument which is a valid stock number as maintained through 'Adjust Inventory Balance' - 'MC - Branch to User'.

If the Liquidation of MC causes reduction in the eligibility of the LMC for that customer reference number, then auto liquidation of LMCs held by the customer is done. Hence this control number is used for the partially liquidated LMCs.

Pay-in option

Specify the pay option from the following drop down list:

- Cash
- Account Transfer

Account No/GL code

Upon selection of pay-in-option as cash, you should select the GL code (as maintained in pay-in parameters) from which the contract value would be debited. If the GL code is not selected then upon save system would default the relevant GL code from pay-in parameter maintenance.

For pay-in-option as account transfer, you should specify the customer account number (linked to the selected CIF). System would allow only LCY accounts to be selected.

Remarks

Specify any additional remarks for the Payment.

Charge Group

System defaults the charge group associated with the CIF to be used for the contract. You can modify the charge group of the contract.

Denomination Details

For cash payment, you can maintain denomination details. You should operationally maintain appropriate denomination details for the amount settled across counter which is not validated by the system.

7. Accounting Entries and Advices

7.1 Introduction

This Annexure contains details of the suggested accounting roles and events related to the MB module of Oracle FLEXCUBE. The annexure lists details of the suggested accounting entries, event-wise. Supporting Advices and Notifications are also listed in this chapter.

7.2 MB Events

The following is an exhaustive list of events that are part of millionaire certificate product maintenance. In the subsequent paragraphs we shall examine the accounting entries for each of the events listed below.

Event Code	Event Description
BOOK	MC/LMC Book
INIT	MC/LMC Issuance
RIMC	MC/LMC Re-issuance
WIMC	MC Issuance to winners
LIQD	MC/LMC Liquidation
ROLL	LMC rollover
LMCA	LMC Monthly amortization
PROV	MC Monthly provision
CLOS	LMC Closure
REVR	Reversal

7.3 Accounting Entries

No accounting entries are maintained for BOOK and CLOS events. The accounting entries are maintained for other events as mentioned below:

7.3.1 MC Issuance – Cash/Cheque/Credit Card/Account transfer

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
INIT	MC_CUST_AC_GL	Dr	CERT_AMT	Certificate value * No. of certificates
INIT	MC_CUST_AC_GL	Dr	<Charge-Class>_AMT	Issuance charge
INIT	MC_LIAB_GL	Cr	CERT_AMT	Certificate value * No. of certificates
INIT	<Charge-Class>_INC	Cr	<Charge-Class>_AMT	Issuance charge

7.3.2 MC Re-issuance

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
RIMC	MC_CUST_AC_GL	Dr	<Charge-Class>_AMT	Re-Issuance charge
RIMC	<Charge-Class>_GL	Cr	<Charge-Class>_AMT	

7.3.3 MC Issuance to winners

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
WIMC	HO_AC_CPC	Dr	CERT_AMT	Certificate value * No. of certificates
WIMC	MC_LIAB_GL	Cr	CERT_AMT	

7.3.4 MC Liquidation/Encashment

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
LIQD	MC_LIAB_GL	Dr	CERT_AMT	Certificate value * No. of certificates
LIQD	MC_CUST_AC_GL	Cr	CERT_AMT	
LIQD	MC_CUST_AC_GL	Dr	<Charge-Class>_AMT	Pre-encashment fee
LIQD	MC_INCOME_GL	Cr	<Charge-Class>_AMT	

7.3.5 MC Monthly Provisioning

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
PROV	MC_EXP_GL	Dr	PROV_AMT	Monthly provision amount. This would trigger an interbranch accounting entry (Debit the local branch and credit the HO).
PROV	MC_PROV_GL	Cr	PROV_AMT	

7.3.6 MC Reversal

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
REVR	MC_CUST_AC_G L	Dr	CERT_AMT	Certificate value * No. of certificates (Negative amount)
REVR	MC_LIAB_GL	Cr	CERT_AMT	Certificate value * No. of certificates (Negative amount)

7.3.7 LMC Issuance

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
INIT	LMC_ASSET_GL	Dr	CERT_AMT	Certificate value *
INIT	LMC_LIAB_GL	Cr	CERT_AMT	No. of certificates
INIT	MC_CUST_AC_GL	Dr	INT_AMT	Issuance price *
INIT	LMC_ADV_INT_G L	Cr	INT_AMT	No. of LMC issued

7.3.8 LMC Manual Roll-over

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
ROLL	MC_CUST_AC_GL	Dr	INT_AMT	Issuance price * No. of LMC issued
ROLL	LMC_ADV_INT_G L	Cr	INT_AMT	

7.3.9 LMC Cancellation

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
LIQD	LMC_LIAB_GL	Dr	CERT_AMT	Certificate value * No. of certificates

LIQD	LMC_ASSET_GL	Cr	CERT_AMT	
LIQD	LMC_ADV_INT_GL	Dr	UNAMORTIZED_INT_AMT	Unamortized interest amount
LIQD	LMC_INT_INCOME_GL	Cr	UNAMORTIZED_INT_AMT	

7.3.10 LMC Monthly Amortization

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
LMCA	LMC_ADV_INT_GL	Dr	AMORTIZE_INT_AMT	Amortized interest amount
LMCA	LMC_INT_INCOME_GL	Cr	AMORTIZE_INT_AMT	

7.3.11 LMC Reversal

Event	Accounting Role	Dr/Cr Ind	Amount tag	Amount tag Description
REVR	LMC_ASSET_GL	Dr	CERT_AMT	Certificate value * (Negative Amount)
REVR	LMC_LIAB_GL	Cr	CERT_AMT	No. of certificates (Negative Amount)
REVR	MC_CUST_AC_GL	Dr	INT_AMT	Issuance price * (Negative Amount)
REVR	LMC_ADV_INT_GL	Cr	INT_AMT	No. of LMC issued (Negative Amount)

7.4 Advices

System supports the below mentioned advices:

Event	Advice Name	Advice Description	Supported Field Tags	Field Tag Description
-------	-------------	--------------------	----------------------	-----------------------

INIT/ RIMC/ WIMC MB_ISSUE Millionaire Certificate Issuance	_CUST-NAME1_	Customer Name
	BRANCH-NAME	Branch Name
	_BOOK_DATE_	Booking Date
	_VALUE_DATE_	Value Date
	_ORIGINAL_PURCHASE_DATE_	Original Purchase Date
	_CERT_START_NUM_	Certificate Start Number
	_CERT_END_NUM_	Certificate End Number
	_NUM_CERT_	Number of Certificates
	_CERT_AMT_	Certificate Amount
	_CONTROL_NUM_	Control Number
	_CONTRACT_REF_NO_	Contract Reference Number

7.5 Notification:

System supports gateway notification for the below mentioned events:

Event Code	Event Description
INIT	MC/LMC Issuance
RIMC	MC/LMC Re-issuance
WIMC	MC Issuance to winners
LIQD	MC/LMC Liquidation
ROLL	LMC rollover

8. Function ID Glossary

M

MBBEODFN	3-7	MBDTRONL	5-1
MBDCMAP	5-9	MBDTRPAY	6-1
MBDCUBAL	5-8	MBSDRMNT	3-7
MBDDRMNT	3-5	MBSMBPAY	3-2
MBDMBPAY	3-1	MBSMPROV	3-4
MBDMPROV	3-3	MBSPRMNT	4-5
MBDPRMNT	4-1	MBSTRONL	5-7