

ORACLE®

PEOPLESOFT

PeopleSoft FSCM 9.2: Asset Lifecycle Management Fundamentals

December 2013

ORACLE®

PeopleSoft FSCM 9.2: Asset Lifecycle Management Fundamentals
CDSKU fscm92pbr2
Copyright © 1992, 2013, Oracle and/or its affiliates. All rights reserved.

Trademark Notice

Oracle and Java are registered trademarks of Oracle and/or its affiliates. Other names may be trademarks of their respective owners.

Intel and Intel Xeon are trademarks or registered trademarks of Intel Corporation. All SPARC trademarks are used under license and are trademarks or registered trademarks of SPARC International, Inc. AMD, Opteron, the AMD logo, and the AMD Opteron logo are trademarks or registered trademarks of Advanced Micro Devices. UNIX is a registered trademark of The Open Group.

License Restrictions Warranty/Consequential Damages Disclaimer

This software and related documentation are provided under a license agreement containing restrictions on use and disclosure and are protected by intellectual property laws. Except as expressly permitted in your license agreement or allowed by law, you may not use, copy, reproduce, translate, broadcast, modify, license, transmit, distribute, exhibit, perform, publish, or display any part, in any form, or by any means. Reverse engineering, disassembly, or decompilation of this software, unless required by law for interoperability, is prohibited.

Warranty Disclaimer

The information contained herein is subject to change without notice and is not warranted to be error-free. If you find any errors, please report them to us in writing.

Restricted Rights Notice

If this is software or related documentation that is delivered to the U.S. Government or anyone licensing it on behalf of the U.S. Government, the following notice is applicable:

U.S. GOVERNMENT END USERS: Oracle programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, delivered to U.S. Government end users are "commercial computer software" pursuant to the applicable Federal Acquisition Regulation and agency-specific supplemental regulations. As such, use, duplication, disclosure, modification, and adaptation of the programs, including any operating system, integrated software, any programs installed on the hardware, and/or documentation, shall be subject to license terms and license restrictions applicable to the programs. No other rights are granted to the U.S. Government.

Hazardous Applications Notice

This software or hardware is developed for general use in a variety of information management applications. It is not developed or intended for use in any inherently dangerous applications, including applications that may create a risk of personal injury. If you use this software or hardware in dangerous applications, then you shall be responsible to take all appropriate fail-safe, backup, redundancy, and other measures to ensure its safe use. Oracle Corporation and its affiliates disclaim any liability for any damages caused by use of this software or hardware in dangerous applications.

Third Party Content, Products, and Services Disclaimer

This software or hardware and documentation may provide access to or information on content, products, and services from third parties. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to third-party content, products, and services. Oracle Corporation and its affiliates will not be responsible for any loss, costs, or damages incurred due to your access to or use of third-party content, products, or services.

Alpha and Beta Draft Documentation Notice

If this document is in preproduction status:

This documentation is in preproduction status and is intended for demonstration and preliminary use only. It may not be specific to the hardware on which you are using the software. Oracle Corporation and its affiliates are not responsible for and expressly disclaim all warranties of any kind with respect to this documentation and will not be responsible for any loss, costs, or damages incurred due to the use of this documentation.

Contents

- Preface.....xiii**
 - Understanding the PeopleSoft Online Help and PeopleBooks..... xiii
 - PeopleSoft Hosted Documentation..... xiii
 - Locally Installed Help..... xiii
 - Downloadable PeopleBook PDF Files..... xiii
 - Common Help Documentation..... xiii
 - Field and Control Definitions..... xiv
 - Typographical Conventions..... xiv
 - ISO Country and Currency Codes..... xv
 - Region and Industry Identifiers..... xv
 - Access to Oracle Support..... xv
 - Documentation Accessibility..... xvi
 - Using and Managing the PeopleSoft Online Help..... xvi
 - PeopleSoft FSCM Related Links..... xvi
 - Contact Us..... xvi
 - Follow Us..... xvi
- Chapter 1: Getting Started with PeopleSoft Asset Lifecycle Management Fundamentals..... 19**
 - Getting Started with PeopleSoft Asset Lifecycle Management Fundamentals..... 19
 - PeopleSoft Asset Lifecycle Management Application Fundamentals Overview..... 19
 - Other Sources of Information..... 20
 - Implementation Considerations..... 20
- Chapter 2: Navigating in PeopleSoft Asset Lifecycle Management..... 21**
 - Navigating in PeopleSoft Asset Lifecycle Management..... 21
 - PeopleSoft Asset Lifecycle Management Custom Navigation..... 21
 - Pages Used to Navigate in Asset Lifecycle Management..... 21
- Chapter 3: Understanding PeopleSoft Asset Lifecycle Management..... 29**
 - Understanding PeopleSoft Asset Lifecycle Management..... 29
 - Understanding the PeopleSoft Asset Management Lifecycle..... 29
 - Understanding the Asset Repository..... 30
 - Implementing PeopleSoft Asset Lifecycle Management..... 33
- Chapter 4: Establishing PeopleSoft Asset Management Business Units..... 35**
 - Establishing PeopleSoft Asset Management Business Units..... 35
 - Understanding Asset Management Business and Cash Generating Units..... 35
 - Creating PeopleSoft Asset Management Business Units..... 38
 - Pages Used to Create PeopleSoft Asset Management Business Units..... 38
 - Prerequisites..... 40
 - AM Business Unit Definition Page..... 40
 - Open Period Update Page..... 46
 - VAT Defaults Setup Page..... 46
 - Business Unit info for Japan Page..... 51
 - Business Unit/Book Definition Page..... 53
 - Round Options Page..... 57
 - Depreciation Close List Page..... 58
 - Business Unit/Book Feature Page..... 59
 - Interface Options Page..... 62
 - Creating PeopleSoft Asset Management Cash Generating Units..... 67
 - Page Used to Create Cash Generating Units..... 68

Understanding Cash Generating Units.....	68
Prerequisites to Creating Cash Generating Units.....	68
Cash Generating Unit Definition Page.....	68
Chapter 5: Establishing Asset Processing.....	71
Establishing Asset Processing.....	71
Understanding Asset Processing.....	71
Prerequisites.....	72
Defining Common Tables to Manage Assets.....	72
Pages Used to Define Common Tables.....	73
Defining Asset Attributes.....	73
Pages Used to Define Asset Attributes.....	75
Asset Classes Page.....	78
Payment Schedules page.....	79
FERC Code Page.....	81
Joint Venture Allocation Page.....	82
Maintenance Types Page.....	82
Units of Production Page.....	83
Maintaining Indexes and Units of Production Tables.....	84
Defining Asset Physical Definitions.....	85
Agencies Page.....	85
Area Definition Page.....	86
Asset Type Options Page.....	87
Define Asset Subtype Page.....	89
Define Asset Attribute Page.....	90
Define Property Subclass Page.....	91
Hazardous Codes Page.....	92
Meter Type Definition Page.....	92
Setting Up Asset Warranties.....	94
Standard Warranties Page.....	95
Warranty Templates Page.....	97
Equipment Parts List Page.....	98
Criticality Codes Page.....	98
Setting Up Asset Profiles.....	99
Pages Used to Set Up Asset Profiles.....	100
Understanding Asset Profiles.....	101
Asset Profiles – Definition Page.....	101
Asset Profiles - Depreciation Page.....	105
Depreciation Method Information Page.....	110
(ARG, BRA, and MEX) Asset Profiles - Inflation Information page.....	111
(JPN) Salvage Rounding Options page.....	112
Asset Profiles - Tax Page.....	114
Child Asset Inheritance Page.....	118
Establishing Asset Ownership.....	119
Pages Used to Establish Asset Ownership.....	119
Understanding Asset Ownership.....	119
Asset Owner Page.....	120
Asset Owner User Page.....	120
Asset Owners to Operators Page.....	121
Defining On-Demand Processing for PeopleSoft Asset Management.....	122
Page Used to Define On-Demand Processing.....	122
Understanding On-Demand Processing for PeopleSoft Asset Management.....	123

Setting Up Reporting Options.....	123
Pages Used to Set Up Reporting Options.....	123
Understanding Reporting Options.....	124
Reporting Drilldown Fields Page.....	125
(Optional) User Preferences - Asset Management Page.....	125
Report Suffix Page.....	125
ChartField Format Template Page.....	126
Report Fields Format Template Page.....	127
Chapter 6: Setting Up Accounting Entry and Financial Processing for PeopleSoft Asset Management.....	131
Setting Up Accounting Entry and Financial Processing for PeopleSoft Asset Management.....	131
Understanding Accounting Entry and Financial Processing.....	131
Defining Accounting Entries.....	131
Pages Used to Define Accounting Entry for PeopleSoft Asset Management.....	132
Understanding Accounting Entry Options.....	134
Prerequisites.....	135
Transaction Codes Page.....	135
Accounting Entry Template IDs Page.....	137
Accounting Entry Templates Page.....	138
Accounting Templates in Mass Page.....	141
InterUnit Transfer Definition Page.....	145
Defining Financial Processing for PeopleSoft Asset Management.....	149
Pages Used to Define Financial Processing.....	149
Understanding Financial Processing in PeopleSoft Asset Management.....	151
Categories Page.....	152
Cost Types Page.....	153
Capitalization Limits Page.....	155
Capitalization Thresholds Page.....	155
Capitalization Threshold Validation Page.....	158
Clearing Reconciliation Page.....	160
Capitalization Threshold Summary Report Page.....	161
Defining Fair Value Processing.....	162
Pages Used to Define Fair Value Processing.....	162
Understanding Fair Value Processing in Asset Management.....	163
Fair Value Valuation Methods Page.....	163
Fair Value Groups Page.....	165
Fair Value Templates Page.....	165
Defining Investment Property.....	168
Pages Used to Define Investment Property in Asset Management.....	168
Understanding Investment Property in Asset Management.....	168
Prerequisites.....	170
Categories Page.....	171
Creating Accounting Entries for Investment Property.....	171
Enabling the Revaluation Process for Investment Property.....	171
Enabling Combination Editing.....	172
Pages Used to Enable Combination Editing in Asset Management.....	172
Understanding Combination Editing in Asset Management.....	173
Business Unit/Book Definition Page.....	174
Combination Editing Options Page.....	175
Defining Document Sequencing.....	176
Pages Used to Define Document Sequencing for PeopleSoft Asset Management.....	177

Understanding Document Sequencing for PeopleSoft Asset Management.....	177
Prerequisites.....	180
Document Type Template Page.....	181
Chapter 7: Setting Up Depreciation Processing.....	183
Setting Up Depreciation Processing.....	183
Understanding Depreciation Processing.....	183
Setting Up Depreciation Calendars.....	184
Page Used to Set Up Depreciation Calendars.....	184
Setting Up Depreciation Conventions.....	184
Pages Used to Set Up Depreciation Conventions.....	185
Understanding Depreciation Conventions.....	185
Convention Builder Page.....	186
Convention Definition Page.....	189
Setting Up Depreciation Schedules.....	190
Page Used to Set Up Depreciation Schedules.....	190
Understanding Depreciation Schedules.....	190
Schedules Page.....	191
Defining Depreciation Terms and Rates.....	192
Pages Used to Define Depreciation Terms.....	192
Depreciation Terms Page.....	193
Defining Depreciation Bonus Information.....	194
Page Used to Define Depreciation Bonus.....	194
Depreciation Bonus Page.....	194
Defining Depreciation Limits.....	196
Page Used to Define Depreciation Limits.....	196
Depreciation Limits Page.....	197
(DEU) Setting Up Multi-shift Codes.....	197
Page Used to Set Up Multi-shift Codes.....	197
Understanding Multi-shift Codes.....	197
Enabling Options to Stop Negative Depreciation.....	200
Pages Used to Set Up the Stop Depreciation Option.....	200
Understanding the Option to Stop Negative Depreciation.....	200
Chapter 8: Setting Up Tax Processing and Tax Reporting.....	203
Setting Up Tax Processing and Tax Reporting.....	203
Understanding Tax Processing and Reporting.....	203
(AUS) Defining VAT Thresholds.....	204
Pages Used to Define VAT Thresholds.....	204
Understanding VAT Thresholds.....	204
Thresholds-VAT Page.....	204
(AUS) Defining Asset Unit Aggregate RD.....	206
Page Used to Define Asset Unit Aggregate RD.....	206
Asset Unit Aggregate RD - AUS Page.....	206
Defining Tax Credits.....	207
Pages Used to Define Tax Credits.....	207
Understanding Tax Credits.....	207
Credits Page.....	207
(FRA) Defining Business Tax by Location.....	208
Page Used to Define Business Tax by Location.....	209
(CAN, IND, and USA) Defining and Maintaining Tax Classes.....	209
Page Used to Define Tax Class.....	209
Understanding How to Use Tax Classes.....	209

Classes Page.....	210
(IND) Setting Up Tax Asset Blocks.....	212
Page Used to Set Up Asset Blocks.....	212
Understanding Asset Blocks.....	212
Asset Block Page.....	213
(IND) Defining Tax Entities and Tax Options.....	213
Pages Used to Define Tax Entities and Tax Options.....	214
Entity Page.....	214
Tax Options Page.....	216
(JPN) Defining Owner Information and Return Information.....	217
Pages Used to Enter Tax Roll Report Information.....	217
Entering Japanese Tax Information.....	218
Setting Up Retirement Basis Reduction Codes.....	218
Page Used to Set Up Retirement Basis Codes.....	218
Retirement Basis Reduction Page.....	218
(USA) Defining Qualified Investment Codes.....	218
Page Used to Define Qualified Investment Codes.....	219
Understanding Qualified Investment Codes.....	219
Defining Property Tax Authorities.....	219
Page Used to Define Property Tax Authority Codes.....	219
Chapter 9: Integrating PeopleSoft Asset Management with Other Products.....	221
Integrating PeopleSoft Asset Management with Other Products.....	221
Understanding How PeopleSoft Asset Management Integrates with Other Applications.....	221
Integrating with PeopleSoft Billing.....	226
Understanding How to Integrate with PeopleSoft Billing.....	226
Enabling PeopleSoft Billing Integration with PeopleSoft Asset Management.....	229
Integrating with Budgeting.....	230
Pages Used to Integrate with Budgeting.....	230
Understanding How to Integrate with Budgeting.....	230
Using the Budgets Interface.....	230
Integrating with General Ledger.....	231
Understanding How to Integrate with General Ledger.....	231
Integrating Asset Management with IT Asset Management.....	231
Understanding How to Integrate with IT Asset Management.....	232
Integrating Asset Management with Maintenance Management.....	233
Understanding How to Integrate with Maintenance Management.....	233
Integrating Asset Management with Real Estate Management.....	234
Pages Used to Integrate Asset Management with Real Estate Management.....	235
Understanding How to Integrate with Real Estate Management.....	236
Exchanging Asset Data with CAFM.....	238
Prerequisites.....	239
Establishing Space Allocation Basis for CAFM.....	240
CAFM Property Integration Page.....	241
CAFM Department Integration Page.....	242
Exchanging Employee Information with CAFM.....	243
Processing PeopleSoft Asset Management, Purchasing, and Payables Transactions.....	243
Understanding PeopleSoft Asset Management, Purchasing, and Payables Transactions.....	243
Consolidating Requisition and Purchase Order Lines for Asset Components.....	245
Processing PeopleSoft Payables Transactions with Asset Management.....	249
Processing PeopleSoft Asset Management Lease Payments in PeopleSoft Payables.....	252
Processing PeopleSoft Purchasing Transactions with PeopleSoft Asset Management.....	253

Processing Purchasing and Payables Transactions with Asset Management.....	256
Pages Used to Process Purchasing and Payables Transactions with Asset Management.....	256
Pre-AM Financial Page and Pre-AM Physical Page.....	257
Procurement Group Inquiry Page.....	261
Payables/Purchasing Interface Page.....	262
Integrating with PeopleSoft Project Costing.....	264
Understanding PeopleSoft Project Costing Integration.....	264
Integrating with Strategic Sourcing.....	266
Understanding Integrating with Strategic Sourcing.....	266
Previewing Data in the Loader Tables.....	267
Pages Used to Preview Data in the Loader Tables.....	267
Understanding Previewing Data in the Loader Tables.....	267
Financial Transactions Page.....	268
Physical Transactions A Page and Physical Transactions B Page.....	269
Approving Load Lines.....	272
Pages Used to Approve Load Lines.....	272
Approve Financial Page.....	272
Approve Physical A Page and Approve Physical B Page.....	274
Running the Transaction Loader.....	274
Page Used to Run the Transaction Loader.....	275
Understanding the Transaction Loader Run Process.....	275
Load Transactions into AM Page.....	275
Consolidating and Unitizing Assets.....	277
Pages Used to Consolidate and Unitize Assets.....	278
Understanding the Consolidation and Unitization of Assets.....	278
Consolidate Assets - FROM Assets Page.....	279
Consolidate Assets – TO Asset Page.....	281
Unitize Assets – FROM Asset Page.....	282
Proportional Unitization Defaults Page.....	282
Unitize Assets – TO Assets Page.....	282
Exporting Property Tax Data to Third-Party Tax Systems.....	284
Page Used to Export Property Tax Data to Third-Party Tax Systems.....	284
Load Property Tax Table Page.....	284
Importing Asset Data by Using the Excel to Component Interface Utility.....	285
Chapter 10: Configuring PeopleSoft Asset Lifecycle Management Background Processes.....	287
Configuring PeopleSoft Asset Lifecycle Management Background Processes.....	287
Configuring Temporary Tables for Background Processing.....	287
Chapter 11: Setting Up and Using Approval Framework in Asset Management.....	289
Understanding Approval Framework in Asset Management.....	289
Approval Framework Process Flow in Asset Management.....	290
Completing the Approval Transaction Registry and Configuration.....	290
Pages Used to Complete the Approval Transaction Registry and Configuration.....	291
Register Transactions Page.....	291
Configure Transactions Page.....	293
Creating or Modifying Notification Template Definitions.....	295
Pages Used to Create or Modify Notification Templates.....	295
Generic Template Definition Page - AM Disposal Line Request Template.....	295
Generic Template Definition Page - AM Disposal Line Approved Template.....	296
Generic Template Definition Page – AM Disposal Line Denied Template.....	297
Defining User Lists for Approval Framework.....	298
Pages Used to Define User Lists or Asset Owners.....	299

User List Definition Page..... 299

Asset Owner User Page..... 300

Setting Up Approval Process Definitions..... 301

Pages Used to Define Approval Process Rules..... 302

Setup Process Definitions Page..... 302

Criteria Definition Page..... 304

Approval Path Definition Page..... 304

Approval Step Definition Page..... 304

Example of Approval Framework Setup for Asset Disposal..... 305

Review or Update Requester and Approvers User Lists..... 306

Assign Asset Owner Permissions..... 306

Review or Update Generic Templates..... 306

Review or Update Approval Process Setup..... 306

Example: Request and Approval of Asset Disposal..... 307

Preface

Understanding the PeopleSoft Online Help and PeopleBooks

The PeopleSoft Online Help is a website that enables you to view all help content for PeopleSoft Applications and PeopleTools. The help provides standard navigation and full-text searching, as well as context-sensitive online help for PeopleSoft users.

PeopleSoft Hosted Documentation

You access the PeopleSoft Online Help on Oracle's PeopleSoft Hosted Documentation website, which enables you to access the full help website and context-sensitive help directly from an Oracle hosted server. The hosted documentation is updated on a regular schedule, ensuring that you have access to the most current documentation. This reduces the need to view separate documentation posts for application maintenance on My Oracle Support, because that documentation is now incorporated into the hosted website content. The Hosted Documentation website is available in English only.

Locally Installed Help

If your organization has firewall restrictions that prevent you from using the Hosted Documentation website, you can install the PeopleSoft Online Help locally. If you install the help locally, you have more control over which documents users can access and you can include links to your organization's custom documentation on help pages.

In addition, if you locally install the PeopleSoft Online Help, you can use any search engine for full-text searching. Your installation documentation includes instructions about how to set up Oracle Secure Enterprise Search for full-text searching.

See *PeopleTools 8.53 Installation* for your database platform, "Installing PeopleSoft Online Help." If you do not use Secure Enterprise Search, see the documentation for your chosen search engine.

Note: Before users can access the search engine on a locally installed help website, you must enable the Search portlet and link. Click the Help link on any page in the PeopleSoft Online Help for instructions.

Downloadable PeopleBook PDF Files

You can access downloadable PDF versions of the help content in the traditional PeopleBook format. The content in the PeopleBook PDFs is the same as the content in the PeopleSoft Online Help, but it has a different structure and it does not include the interactive navigation features that are available in the online help.

Common Help Documentation

Common help documentation contains information that applies to multiple applications. The two main types of common help are:

- Application Fundamentals

- Using PeopleSoft Applications

Most product lines provide a set of application fundamentals help topics that discuss essential information about the setup and design of your system. This information applies to many or all applications in the PeopleSoft product line. Whether you are implementing a single application, some combination of applications within the product line, or the entire product line, you should be familiar with the contents of the appropriate application fundamentals help. They provide the starting points for fundamental implementation tasks.

In addition, the *PeopleTools: PeopleSoft Applications User's Guide* introduces you to the various elements of the PeopleSoft Pure Internet Architecture. It also explains how to use the navigational hierarchy, components, and pages to perform basic functions as you navigate through the system. While your application or implementation may differ, the topics in this user's guide provide general information about using PeopleSoft Applications.

Field and Control Definitions

PeopleSoft documentation includes definitions for most fields and controls that appear on application pages. These definitions describe how to use a field or control, where populated values come from, the effects of selecting certain values, and so on. If a field or control is not defined, then it either requires no additional explanation or is documented in a common elements section earlier in the documentation. For example, the Date field rarely requires additional explanation and may not be defined in the documentation for some pages.

Typographical Conventions

The following table describes the typographical conventions that are used in the online help.

<i>Typographical Convention</i>	<i>Description</i>
Key+Key	Indicates a key combination action. For example, a plus sign (+) between keys means that you must hold down the first key while you press the second key. For Alt+W, hold down the Alt key while you press the W key.
... (ellipses)	Indicate that the preceding item or series can be repeated any number of times in PeopleCode syntax.
{ } (curly braces)	Indicate a choice between two options in PeopleCode syntax. Options are separated by a pipe ().
[] (square brackets)	Indicate optional items in PeopleCode syntax.
& (ampersand)	When placed before a parameter in PeopleCode syntax, an ampersand indicates that the parameter is an already instantiated object. Ampersands also precede all PeopleCode variables.
⇒	This continuation character has been inserted at the end of a line of code that has been wrapped at the page margin. The code should be viewed or entered as a single, continuous line of code without the continuation character.

ISO Country and Currency Codes

PeopleSoft Online Help topics use International Organization for Standardization (ISO) country and currency codes to identify country-specific information and monetary amounts.

ISO country codes may appear as country identifiers, and ISO currency codes may appear as currency identifiers in your PeopleSoft documentation. Reference to an ISO country code in your documentation does not imply that your application includes every ISO country code. The following example is a country-specific heading: "(FRA) Hiring an Employee."

The PeopleSoft Currency Code table (CURRENCY_CD_TBL) contains sample currency code data. The Currency Code table is based on ISO Standard 4217, "Codes for the representation of currencies," and also relies on ISO country codes in the Country table (COUNTRY_TBL). The navigation to the pages where you maintain currency code and country information depends on which PeopleSoft applications you are using. To access the pages for maintaining the Currency Code and Country tables, consult the online help for your applications for more information.

Region and Industry Identifiers

Information that applies only to a specific region or industry is preceded by a standard identifier in parentheses. This identifier typically appears at the beginning of a section heading, but it may also appear at the beginning of a note or other text.

Example of a region-specific heading: "(Latin America) Setting Up Depreciation"

Region Identifiers

Regions are identified by the region name. The following region identifiers may appear in the PeopleSoft Online Help:

- Asia Pacific
- Europe
- Latin America
- North America

Industry Identifiers

Industries are identified by the industry name or by an abbreviation for that industry. The following industry identifiers may appear in the PeopleSoft Online Help:

- USF (U.S. Federal)
- E&G (Education and Government)

Access to Oracle Support

Oracle customers have access to electronic support through My Oracle Support. For information, visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=info> or visit <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=trs> if you are hearing impaired.

Documentation Accessibility

For information about Oracle's commitment to accessibility, visit the Oracle Accessibility Program website at <http://www.oracle.com/pls/topic/lookup?ctx=acc&id=docacc>.

Using and Managing the PeopleSoft Online Help

Click the Help link in the universal navigation header of any page in the PeopleSoft Online Help to see information on the following topics:

- What's new in the PeopleSoft Online Help.
 - PeopleSoft Online Help accessibility.
 - Accessing, navigating, and searching the PeopleSoft Online Help.
 - Managing a locally installed PeopleSoft Online Help website.
-

PeopleSoft FSCM Related Links

Financial and Supply Chain Management information for Secure Enterprise Search (SES) can be found in PeopleSoft Application Fundamentals documentation. For application specific information, see the "Understanding Search Pages within Components (*PeopleSoft FSCM 9.2: Application Fundamentals*)" topic.

[My Oracle Support](#)

[PeopleSoft Information Portal on Oracle.com](#)

[PeopleSoft Training from Oracle University](#)

[PeopleSoft Video Feature Overviews on YouTube](#)

Contact Us

[Send us your suggestions](#) Please include release numbers for the PeopleTools and applications that you are using.

Follow Us



Get the latest PeopleSoft updates on [Facebook](#).



Follow PeopleSoft on [Twitter@PeopleSoft_Info](#).

Chapter 1

Getting Started with PeopleSoft Asset Lifecycle Management Fundamentals

Getting Started with PeopleSoft Asset Lifecycle Management Fundamentals

This topic provides an overview of the common business processes described in the *PeopleSoft Asset Lifecycle Management (ALM) Fundamentals* documentation.

Because the information in the *PeopleSoft Asset Lifecycle Management (ALM) Fundamentals* documentation involves more than one PeopleSoft product, you need to refer to the *Getting Started* topics for each product for specific implementation and integration information.

The products included in Oracle's PeopleSoft Asset Lifecycle Management suite include:

- PeopleSoft Asset Management.
- PeopleSoft IT Asset Management.
- PeopleSoft Maintenance Management.
- PeopleSoft Real Estate Management.

Related Links

"PeopleSoft Asset Management Overview (*PeopleSoft FSCM 9.2: Asset Management*)"

"IT Asset Management Overview (*PeopleSoft FSCM 9.2: IT Asset Management*)"

"PeopleSoft Real Estate Management Business Process (*PeopleSoft FSCM 9.2: Real Estate Management*)"

"PeopleSoft Maintenance Management Business Processes (*PeopleSoft 9.2: Maintenance Management*)"

PeopleSoft Asset Lifecycle Management Application Fundamentals Overview

This product documentation discusses the following functionality and business processes:

- Using the PeopleSoft Asset Lifecycle Management (ALM) solution and the asset repository.
- Establishing asset management business units and cost generating units.
- Establishing asset processing.
- Setting up accounting entry and financial processing.

- Setting up depreciation processing.
- Setting up tax processing and tax reporting.
- Integrating PeopleSoft Asset Management with other products.
- Understanding the loader table data dictionary.
- Configuring PeopleSoft ALM background processes.

Other Sources of Information

In the planning phase of your implementation, take advantage of all PeopleSoft sources of information, including the installation guides, table-loading sequences, data models, and business process maps. A complete list of these resources is in the product documentation with information on where to find the most up-to-date version of each.

Implementation Considerations

PeopleSoft Enterprise Setup Manager enables you to review a list of setup tasks for your organization for the products that you are implementing. The setup tasks include the components that you must set up, listed in the order in which you must enter data into the component tables, and links to the corresponding documentation.

Asset Management also provides component interfaces to help you load data from the existing system into Asset Management tables. Use the Excel to Component Interface utility with the component interfaces to populate the tables.

See [Importing Asset Data by Using the Excel to Component Interface Utility](#).

Chapter 2

Navigating in PeopleSoft Asset Lifecycle Management

Navigating in PeopleSoft Asset Lifecycle Management

This topic discusses how to navigate in Oracle's PeopleSoft Asset Lifecycle Management.

PeopleSoft Asset Lifecycle Management Custom Navigation

PeopleSoft Asset Lifecycle Management provides custom navigation center pages that contain groupings of folders that support a specific business process, task, or user role.

Note: In addition to the PeopleSoft Asset Lifecycle Management custom navigation center pages, PeopleSoft provides menu navigation, standard navigation pages, and PeopleSoft Navigator.

See *PeopleTools: PeopleSoft Applications User's Guide*

Pages Used to Navigate in Asset Lifecycle Management

This table lists the custom navigation Asset Definitions Center pages that are used to navigate throughout the implementation tasks in PeopleSoft Asset Lifecycle Management.

Page Name	Navigation	Usage
Asset Definitions Center	Main Menu, Asset Definitions Center	Access primary Asset Definitions Center menu options and activities.
Business Unit/Book Definition	Click Business Unit/Book Definition on the Asset Definitions Center page.	Access the Business Unit/Book Definition folder that contains options to define business units and books, cash generating units, InterUnit transfer processing, reporting drilldown fields and report suffix for asset report templates.
Asset Management Definition	Click Business Unit/Book Definition on the Asset Definitions Center page; then click Asset Management Definition.	Access the Asset Management Definition component to define business units.
Asset Books	Click Business Unit/Book Definition on the Asset Definitions Center page; then click Asset Books.	Access the Asset Books page to define asset books.

Page Name	Navigation	Usage
InterUnit Transfer Definition	Click Business Unit/Book Definition on the Asset Definitions Center page; then click InterUnit Transfer Definition.	Access the InterUnit Transfer Definition page to define InterUnit transfer processing.
Cash Generating Unit Definition	Click Business Unit/Book Definition on the Asset Definitions Center page; then click CGU Definition.	Access the Cash Generating Unit Definition page to define cash generating units.
Reporting Drilldown Fields	Click Business Unit/Book Definition on the Asset Definitions Center page; then click Reporting Drilldown Fields.	Access the Reporting Drilldown Fields page to enable a detail view by Group ID by ChartField for reporting drilldown.
Report Suffix	Click Business Unit/Book Definition on the Asset Definitions Center page; then click Report Suffix.	Access the Report Suffix page to define report suffixes.
Depreciation Conventions	Click Depreciation Conventions on the Asset Definitions Center page.	Access the Depreciation Conventions folder to build and copy depreciation conventions.
Convention Builder	Click Depreciation Conventions on the Asset Definitions Center page; then click Convention Builder.	Access the Convention Builder page to define parameters for depreciation conventions based on monthly accounting calendars.
Convention Definition	Click Depreciation Conventions on the Asset Definitions Center page; then click Convention Definition.	Access the Convention Definition page to define attributes for depreciation conventions and enter all the dates associated with it.
Convention Multiple Copy	Click Depreciation Conventions on the Asset Definitions Center page; then click Convention Multiple Copy.	Access the Convention Multiple Copy page to copy all conventions associated with a SetID or calendar to another SetID or calendar.
Convention Single Copy	Click Depreciation Conventions on the Asset Definitions Center page; then click Convention Single Copy.	Access the Convention Single Copy page to copy one convention from a SetID or calendar to another convention, SetID or calendar.
Asset Controls	Click Asset Controls on the Asset Definitions Center page.	Access the Asset Controls folder to establish limitations and special characteristics for certain assets.
Define Asset Subtype	Click Asset Controls on the Asset Definitions Center page; then click Asset Subtype.	Access the Define Asset Subtype page to define asset subtypes.
Define Asset Attribute	Click Asset Controls on the Asset Definition Center page; then click Define Asset Attribute.	Access the Define Asset Attribute page to define customizable asset attributes.
Define Property Subclass	Click Asset Controls on the Asset Definition Center page; then click Asset Property Subclass.	Access the Define Property Subclass page to create asset property subclasses.

Page Name	Navigation	Usage
Capitalization Limits	Click Asset Controls on the Asset Definitions Center page; then click Capitalization Limits.	Access the Capitalization Limits page to set up cost limit codes by currency as necessary.
Asset Classes	Click Asset Controls on the Asset Definitions Center page; then click Asset Classes.	Access the Asset Classes page to define asset classes.
Categories	Click Asset Controls on the Asset Definitions Center page; then click Categories.	Access the Categories page to establish asset categories, which classify assets by type for accounting entry purposes.
Cost Types	Click Asset Controls on the Asset Definitions Center page; then click Cost Types.	Access the Cost Types page to define cost types.
Hazardous Codes	Click Asset Controls on the Asset Definitions Center page; then click Hazardous Codes.	Access the Hazardous Codes page to define hazardous-asset codes.
Retirement Basis Reduction	Click Asset Controls on the Asset Definitions Center page; then click Retirement Basis Reduction.	Access the Retirement Basis Reduction page to set up retirement basis reduction codes.
Depreciation Options	Click Depreciation Options on the Asset Definitions Center page.	Access the Depreciation Options folder to control and calculate depreciation.
Limits	Click Depreciation Options on the Asset Definitions Center page; then click Limits.	Access the Limits page to specify the maximum amount or percentage of depreciation that you can expense on your assets for each year of life.
Multi-Shift Codes	Click Depreciation Options on the Asset Definitions Center page; then click Multi-Shift Codes.	Access the Multi-Shift Codes page to enter rates by which depreciation should be increased based on the number of production shifts an asset is used.
Rate - User Defined	Click Depreciation Options on the Asset Definitions Center page; then click Rate - User Defined.	Access the Rate-User Defined page to establish rates by useful life.
Units of Production	Click Depreciation Options on the Asset Definitions Center page; then click Units of Production.	Access the Units of Production page to set up units of production depreciation method definitions.
Terms Definition	Click Depreciation Options on the Asset Definitions Center page; then click Terms Definition.	Access the Terms Definition page to enter terms to be applied to depreciation in a global environment. Terms stored here can be selected when you are specifying depreciation methods and have enabled global options. These terms are used to alter depreciation calculations so that they comply with specific country requirements.

Page Name	Navigation	Usage
Schedules	Click Depreciation Options on the Asset Definition Center page; then click Schedules.	Access the Schedules page to define asset depreciation schedules.
Period Allocation	Click Depreciation Options on the Asset Definitions Center page; then click Period Allocation.	Access the Period Allocation page to create depreciation expense allocation tables.
Residual Rate Definition	Click Depreciation Options on the Asset Definition Center page; then click Residual Rate Definition .	Access the Residual Rate Definition page to define residual tax rates.
Location/Ownership	Click Location/Ownership on the Asset Definitions Center page.	Access the Location/Ownership folder to define asset location and ownership tables.
Area Definition	Click Location/Ownership on the Asset Definitions Center page; then click Area Definition.	Access the Area Definition page to define asset areas.
Location Definition	Click Location/Ownership on the Asset Definitions Center page; then click Location Definition.	Access the Location Definition page to define locations.
Asset Owner	Click Location/Ownership on the Asset Definitions Center page; then click Define Asset Owners.	Access the Asset Owner page to define role-based asset owners and assign assets to the owner.
Assign Owners to Operators	Click Location/Ownership on the Asset Definitions Center page; then click Assign Owners to Operators.	Access the Assign Owners to Operators page to assign operators to owners.
Tax Information	Click Tax Information on the Asset Definitions Center page.	Access the Tax Information folder to define tax controls and identification.
Business Tax by Location	Click Tax Information on the Asset Definitions Center page; then click Business Tax by Location.	Access the Business Tax by Location page to enter and store tax rates by location.
Asset Block	Click Tax Information on the Asset Definitions Center page; then click Asset Block.	Access the Asset Block page to define assets blocks. This is equivalent to the <i>tax block</i> for India.
Classes	Click Tax Information on the Asset Definitions Center page; then click Classes.	Access the Classes page to set up or review tax classes.
Thresholds-VAT	Click Tax Information on the Asset Definitions Center page; then click Thresholds-VAT.	Access the Thresholds-VAT page to define and store thresholds for a number of adjustment periods.
Credits	Click Tax Information on the Asset Definitions Center page; then click Credits.	Access the Credits page to set up tax credit tables or modify existing tables.

Page Name	Navigation	Usage
Credit Status	Click Tax Information on the Asset Definitions Center page; then click Credit Status.	Access the Credit Status page to set status for tax credits by country.
Owner Information Defn. - JPN	Click Tax Information on the Asset Definitions Center page; then click Owner Information Defn. - JPN.	Access the Owner Information Defn. - JPN page to set up owner information for taxation.
Qualified Investments	Click Tax Information on the Asset Definitions Center page; then click Qualified Investments.	Access the Qualified Investments page to add or modify qualified investment codes.
Entity	Click Tax Information on the Asset Definitions Center page; then click Tax Entity Definition.	Access the Entity page to define the tax reporting entity.
Return Information Defn. - JPN	Click Tax Information on the Asset Definition Center page; then click Return Information Defn. - JPN.	Access the Return Information Defn. - JPN page to define tax return information for Japan.
Financing Information	Click Financing Information on the Asset Definitions Center page.	Access the Financing Information folder to load finance codes and lease payment schedules.
Capital Acquisition Plan Types	Click Financing Information on the Asset Definitions Center page; then click Capital Acquisition Plan Types.	Access the Capital Acquisition Plan (C.A.P.) Types page to set up C.A.P. types.
FERC Code	Click Financing Information on the Asset Definitions Center page; then click FERC Code.	Access the FERC Code page to define FERC codes.
Transaction Codes	Click Financing Information on the Asset Definitions Center page; then click Transaction Codes.	Access the Transaction Codes page to review or modify the transaction codes.
Financing Codes	Click Financing Information on the Asset Definitions Center page; then click Financing Codes.	Access the Financing Codes page to define financing codes to help you analyze your debit and credit relationships for capital-intensive and government projects.
Payment Schedules	Click Financing Information on the Asset Definitions Center page; then click Payment Schedules.	Access the Payment Schedules page to add or modify lease payment schedules.
Profiles	Click Profiles on the Asset Definitions Center page.	Access the Profiles folder to establish Asset Management system controls.
Asset Profiles	Click Profiles on the Asset Definitions Center page; then click Asset Profiles.	Access the Asset Profiles component to define asset profiles and their depreciation, tax and child asset inheritance options by book.

Page Name	Navigation	Usage
Profile Changes in Mass	Click Profiles on the Asset Definitions Center page; then click Profile Changes in Mass.	Access the Profile Changes in Mass page to copy an asset profile from one SetID to another, or to update a profile by changing some of its attributes.
Accounting Entry Templates	Click Accounting Entry Templates on the Asset Definitions Center page.	Access the Accounting Entry Templates folder to define the Accounting Entry Templates.
Accounting Entry Template IDs	Click Accounting Entry Templates on the Asset Definitions Center page; then click Accounting Entry Template IDs	Access the Accounting Entry Template IDs page to create a template ID with options for depreciation features and distribution methods.
Accounting Entry Templates	Click Accounting Entry Templates on the Asset Definitions Center page; then click Accounting Entry Templates.	Access the Accounting Entry Templates page to add or modify accounting entry templates.
Accounting Templates in Mass	Click Accounting Entry Templates on the Asset Definitions Center page; then click Accounting Templates in Mass.	Access the Accounting Templates in Mass page to create one or multiple accounting entry templates for journal templates, cost types, trans codes, and retirement disposal codes in a single process.
ChartField Mapping Template	Click Accounting Entry Templates on the Asset Definition Center page; then click ChartField Mapping Template.	Access the ChartField Mapping Template page to define ChartField mapping templates.
Book Code Distribution Group	Click Accounting Entry Templates on the Asset Definition Center page; then click Book Code Distribution Group.	Access the Book Code Distribution Group page to define book code distribution groups for accounting entries.
Acct Template Book Code Update	Click Accounting Entry Templates on the Asset Definition Center page; then click Acct Template Book Code Update.	Access the Acct Template Book Code Update page to update accounting template for book codes.
Depreciation Allocation	Click Depreciation Allocation on the Asset Definitions Center page.	Access the Depreciation Allocation folder to define allocation parameters.
Allocation Basis Definition	Click Depreciation Allocation on the Asset Definitions Center page; then click Allocation Basis Definition.	Access the Allocation Basis Definition page to define the allocation basis.
Joint Venture Allocation	Click Depreciation Allocation on the Asset Definitions Center page; then click Joint Venture Allocation.	Access the Joint Venture Allocation page to define the percentage of asset ownership allocated to each joint venture participant.
Transaction Groups	Click Depreciation Allocation on the Asset Definitions Center page; then click Transaction Groups.	Access the Transaction Groups page to set up transaction groups for purposes of allocating depreciation.

Page Name	Navigation	Usage
Maintenance Information	Click Maintenance Information on the Asset Definitions Center page.	Access the Maintenance Information folder to define asset maintenance controls and parameters.
Criticality Codes	Click Maintenance Information on the Asset Definitions Center page; then click Criticality Codes.	Access the Criticality Codes page to establish criticality codes and assign a description to them.
Agencies	Click Maintenance Information on the Asset Definitions Center page; then click Agencies.	Access the Agencies page to create agency codes. Keep track of an asset's registration and licenses by using the information set up in Agency tables.
Indexes	Click Maintenance Information on the Asset Definitions Center page; then click Indexes.	Access the Indexes page to set up an index, and subindex.
Insurance Types	Click Maintenance Information on the Asset Definitions Center page; then click Insurance Types.	Access the Insurance Types page to enter different types of insurance, such as liability for automobiles or property.
Maintenance Types	Click Maintenance Information on the Asset Definitions Center page; then click Maintenance Types.	Access the Maintenance Types page to define asset maintenance controls and parameters.
Equipment Parts List	Click Maintenance Information on the Asset Definition Center page; then click Equipment Parts List.	Access the Equipment Parts List page to define equipment parts lists to associate to assets.
Standard Warranties	Click Maintenance Information on the Asset Definition Center page; then click Standard Warranties.	Access the Standard Warranties page to define standard warranties to be associated to assets.
Warranty Templates	Click Maintenance Information on the Asset Definition Center page; then click Warranty Templates.	Access the Warranty Templates page to define warranty templates to be associated with multiple assets at one time.
Meter Type Definition	Click Maintenance Information on the Asset Definition Center page; then click Meter Types.	Access the Meter Type Definition page to define meter types for asset meters.
Depreciation Methods	Click Depreciation Methods on the Asset Definitions Center page.	Access the Depreciation Methods folder to enter and maintain User Defined depreciation methods.
User Defined Variables	Click Depreciation Methods on the Asset Definitions Center page; then click User Defined Variables.	Access the User Defined Variables page to define depreciation variables.
User Defined Methods	Click Depreciation Methods on the Asset Definitions Center page; then click User Defined Methods.	Access the User Defined Methods page to define user-defined depreciation methods.

Page Name	Navigation	Usage
Rate-User Defined	Click Depreciation Methods on the Asset Definitions Center page; then click Rate-User Defined.	Access the Rate-User Defined page to define depreciation rates.
User Defined Methods-Copy	Click Depreciation Methods on the Asset Definitions Center page; then click User Defined Methods-Copy.	Access the User Defined Methods-Copy page to copy user defined depreciation methods.
Generate User Defined Methods	Click Depreciation Methods on the Asset Definitions Center page; then click Generate User Defined Methods.	Access the Generate User Defined Methods to create a user defined depreciation method.

See [PeopleSoft Asset Lifecycle Management Application Fundamentals Overview](#).

See [Understanding Asset Management Business and Cash Generating Units](#).

See [Understanding Asset Processing](#).

See [Understanding Depreciation Processing](#).

See [Understanding Accounting Entry and Financial Processing](#).

See [Understanding Tax Processing and Reporting](#).

Chapter 3

Understanding PeopleSoft Asset Lifecycle Management

Understanding PeopleSoft Asset Lifecycle Management

This topic provides an overview of Oracle's PeopleSoft Asset Lifecycle Management and the Asset Repository Manager (ARM.)

Understanding the PeopleSoft Asset Management Lifecycle

An asset-intensive enterprise requires controlling and managing assets throughout the asset lifecycle: procurement, deployment, maintenance, update, retirement, and analysis. PeopleSoft delivers the Asset Lifecycle Management (ALM) solution to provide complete access to an entire asset portfolio, regardless of asset class, and creating visibility into total cost of ownership by enabling cost tracking associated with acquisition as well as lifetime maintenance and performance of assets.

Enterprise assets cover a broad spectrum of categories including heavy equipment, technology assets, facilities and real estate, and transportation fleets and vehicles. These functionally specific asset categories require software tailored to the unique requirements of each asset category. To address asset differences, specific applications are available within ALM to meet the explicit business processes for each asset category:

- PeopleSoft Asset Management (AM)
- PeopleSoft IT Asset Management (ITAM)
- PeopleSoft Maintenance Management (MM)
- PeopleSoft Real Estate Management (REM)

The foundation product of the PeopleSoft Asset Lifecycle Management solution is PeopleSoft Asset Management. PeopleSoft Asset Management provides a common Asset Repository Manager (ARM), which stores all asset data. The repository provides a single source of truth for physical, financial or operational asset data.

The *Plan to Retire* business process spans from the initial planning and budgeting stage to the end-of-life disposal of assets. Whether the asset lifecycle spans three or thirty years of operational life, the operational components remain the same. PeopleSoft Asset Lifecycle Management, in partnership with the entire suite of PeopleSoft Financials and Supply Chain Management product solutions, provides the information necessary to maximize the utilization of assets.

PeopleSoft defines five phases within the Plan to Retire business process:

- The *Plan* phase includes the prioritization of asset needs and utilization in alignment with corporate objectives. PeopleSoft ALM enables you to collect asset requirements and performance information, forecast asset requirements, assess these requirements to assets currently available and establish an asset plan and budget in line with your strategic direction.
- The *Acquire* phase enables different acquisition processes depending upon asset needs defined in the planning process. Buildings, equipment and other resources may be purchased, leased, constructed, or repurposed.
- The *Deploy* phase focuses on minimizing ramp-up time for getting assets into operation. This may include construction for real estate; setup, configuration and testing for IT assets; or retooling, insurance and certification for major equipment. Additionally, PeopleSoft ALM enables assets to be assigned to users prior to deployment.
- The *Maintain* phase includes capturing and tracking maintenance activity, costs, time and expenses, as well as forecasting maintenance requirements. PeopleSoft ALM allows you to set maintenance budgets, negotiate service level agreements, and plan preventive maintenance schedules.
- The *Retire* phase allows expeditious disposal or sale of assets no longer meeting performance targets set in the planning phase for specific asset types.

Using PeopleSoft Asset Management with the PeopleSoft Budgeting, PeopleSoft Project Costing, PeopleSoft IT Asset Management, PeopleSoft Maintenance Management, or PeopleSoft Real Estate Management products, you can manage and maintain asset acquisitions, deployment, maintenance and disposal as separate projects or as part of ongoing operations.

The pillar of the PeopleSoft ALM product suite is the Asset Repository Manager (ARM). Once the PeopleSoft Asset Management product is established, the asset repository is available to all PeopleSoft products that integrate with PeopleSoft Asset Management.

Note: Without PeopleSoft Asset Management, you cannot have access to the asset repository.

Understanding the Asset Repository

The Asset Repository is the database of assets stored within the PeopleSoft Asset Management system. The Asset Repository Manager accommodates all asset classes: IT, property, and plant equipment, with complete operational and financial data. The Asset Repository provides a single, centralized database that stores and tracks organizational assets physically and financially. Maintaining asset identifying information within a common repository allows sharing asset data across the PeopleSoft FMS, SCM, and HCM suite and with third party applications. Enabling integrated access to asset data accommodates the level of detail preferred by the calling application; for example, some applications require the ability to identify assets at a very high level while others prefer data to be highly granular, thus requiring many asset records to identify all components. The asset repository is required to realize PeopleSoft's ALM solution across all product suites.

The PeopleSoft Asset Lifecycle Management solution provides an integrated framework to manage the physical and financial aspects of organizational assets for the lifetime of the asset.

This centralized repository offers a single source of the truth for organizational asset data eliminating redundancy and inaccuracies in asset reporting. Assets can be associated to represent a hierarchical schema, like components of plant equipment, or a structural breakdown of properties, like a building

broken into segments such as floors and office spaces. The hierarchical display of assets can be viewed graphically by associating the highest-level asset to its subordinate child and component assets. The repository houses a complete history of acquisition details, maintenance history, and cost history for each asset over its operational life.


PeopleSoft currently stores asset information in different databases serving different business process requirements:

- The PeopleSoft Financials and Supply Chain Management (FSCM) database stores financial asset data.
- The PeopleSoft Human Capital Management (HCM) database stores employee assigned assets.

Each database essentially stands alone, has its own unique identification structure and level of data granularity. The shared asset repository enables PeopleSoft to manage the operational requirements of all assets, provides a holistic view of any asset, from any perspective (financial, operational, technical, or custodial) to reduce redundant data, and facilitates sharing common asset information across PeopleSoft's databases and with third party utilities, such as Computer Aided Facility Management (CAFM) and IT asset discovery tools. This diagram demonstrates how the asset repository serves the PeopleSoft enterprise:

Image: Asset Repository in PeopleSoft

Asset Repository in PeopleSoft:



- The FSCM database identifies capital assets that are typically carried at a summarized level to reduce the amount of data required for financial record keeping. For example, a computer workstation is carried as a single asset in the financial asset repository representing all of its components and associated costs.

- SCM carries inventory and spare parts used in the lifetime maintenance of capital assets. The relationship of critical spares to mission critical assets is required for operational and insurance reasons. Organizational assets can be held in inventory until put into service.
- IT asset software utilities like auto-discovery, software delivery, license tracking, usage monitoring, configuration management, contract management and self-healing utilities and maintenance management require a technical view of an asset to maintain appropriate spare parts lists and to facilitate maintenance scheduling of materials and labor. The asset view required by a maintain, repair and operate (MRO) system is more granular than its financial designation, which is summarized to its highest meaningful financial category.

PeopleSoft Asset Management enables you to create equipment parts lists (EPL) that list the individual components of an asset. These asset components roll up to a single Asset ID. This enables you to compare key structures of assets, and assign hierarchies to the real asset, without tracking the individual components. The asset data stored in the Asset Repository includes:

- FSCM's fixed asset data.
- HCM's employee's asset data.
- Asset warehouse; available for reassignment to new custodian, (including noncapital assets assigned to custodians for tracking purposes).
- Non-owned assets (such as field service installed products).
- Spare parts lists, for single assets or asset types.
- Warranties and contracts data elements, for single asset or asset type.
- License information including software license information.
- Inspection schedules and records.
- Preventive maintenance schedules (either manufacturer or user defined), for single asset or asset type.
- Recorded inventory numbers, serial numbers and lot number on those asset components issued from inventory or manufacturer for tracking purposes.
- Technical asset characteristics to identify technology assets, software, and plant equipment.
- Asset configuration information, version control information, usage information, and production history (units produced, hours of operation, and so on.)
- Asset spatial dimensions to accommodate space and computer aided facility management (CAFM) software requirements.
- Reservation information allowing an asset to be reserved for specified time period and retaining all existing financial fixed asset accounting information.
- Custom attributes and supplemental data that you define to apply specific or unique characteristics to an asset.
- Different meaningful levels of criticality assigned to an asset.
- A responsible crew assigned to an asset.

- A long description of an asset.
- The physical location of an asset defined by region, location, and area.
- Multiple attachments for a single asset.

The asset repository accommodates many distinct asset groupings including Parent-Child, group assets, composite assets and multiple organizational perspectives: for example, by custodian, department, asset component, and financial class.

Consult all of the product documentation cited for comprehensive information about specific functionality, features and business processes used in conjunction with the asset repository.

Implementing PeopleSoft Asset Lifecycle Management

PeopleSoft provides a set of documentation components that complement each other to present all the information you need to implement PeopleSoft Asset Management.

To implement PeopleSoft Asset Management, you will find the information required to set up the tables and options used by PeopleSoft Asset Management and the other PeopleSoft ALM products in this documentation as well as the following resources:

- *PeopleSoft Application Fundamentals*
- *PeopleSoft Global Options and Reports*
- *PeopleSoft Asset Management*
- *PeopleSoft IT Asset Management*
- *PeopleSoft Maintenance Management*
- *PeopleSoft Real Estate Management*

Because the information you may need to fully implement PeopleSoft Asset Management involves more than one PeopleSoft product, you need to refer to the *Getting Started* topic in each product document for specific implementation and integration information.

Use the *PeopleSoft Applications Fundamentals* product documentation to find detailed information about the following functionality and processes:

- Defining financials and supply chain management common definitions
- Setting installation options for PeopleSoft applications
- Defining user preferences
- Securing your system
- Defining and using ChartFields
- Editing ChartField combinations
- Configuring ChartFields

- Summarizing ChartFields using trees
- Using entry events
- Using alternate accounts
- Defining accounting calendars
- Setting up ledgers
- Using journal generator
- Using interunit and intraunit accounting and ChartField inheritance
- Processing allocations
- Setting up on-demand processing

Use the *PeopleSoft Asset Lifecycle Management Fundamentals* product documentation to find detailed information about setting up the following functionality and processes:

- Establishing asset management business units and cash generating units
- Establishing asset processing, including defining asset attributes, profiles, ownership and reporting options
- Setting up accounting entry and financial processing
- Setting up depreciation processing
- Setting up tax processing and tax reporting
- Integrating with other products
- Configuring background processing for assets

Establishing PeopleSoft Asset Management Business Units

Establishing PeopleSoft Asset Management Business Units

This topic provides an overview of asset management business and cash generating units and discusses how to:

- Create asset management business units.
- Create asset management cash generating units.

Note: Required: You must complete the tasks discussed in this topic to implement PeopleSoft Asset Management.

Understanding Asset Management Business and Cash Generating Units

You determine how to define business units in PeopleSoft Asset Management to best facilitate asset management processing within your organization. You can set up an asset management business unit for each legal entity in your organization. You could, for example, have asset management activities processed by a central asset management department which will interface with and manage assets for each business unit. Alternatively, you could set up one business unit for each plant or branch office of your company, enabling these entities to manage their own assets independently while sending journals to a common general ledger business unit. You should establish your business units in the manner that best suits your organizational, structural, and reporting needs.

TableSet Sharing and PeopleSoft Trees

When you plan your business unit structure, you need to be familiar with TableSets, which are used in all PeopleSoft Financials products. The accounting structure and processing rules for each PeopleSoft application are defined in a series of control tables. A *TableSet* is a group of rows across control tables upon which you define the accounting structure for each of your business units, such as asset management book definitions, asset profiles, depreciation tables, tax classes, and so forth. For a business unit to process transactions, it must have an associated TableSet Control.

A setID identifies each TableSet. You can have as many setIDs as you want. However, using numerous setIDs creates complex TableSet sharing. You must create at least one setID, even if you do not use TableSet sharing.

PeopleSoft provides a tool called Tree Manager to group business units together into a hierarchical structure. Tree Manager and your business unit structure provide a mechanism for defining reporting parameters.

PeopleSoft Financials uses setID-driven trees. So that Asset Management trees will work properly, the setID assigned to the record group for Tree Node and Tree Level Tables (FS_21) for each business unit *must* equal the business unit value. If the setID for FS_21 does not equal the business unit value, you cannot easily access your assets from the correct asset tree.

When you use the Real Estate application, you will define a default tree for the business unit. The tree names available will depend on the trees you have defined. Plan your tree definitions with business unit definitions in mind.

Note: Each time you create a business unit, whether you copy the TableSet Control from another business unit or create a generic TableSet sharing setup, the system automatically establishes the setID for the Projects record group (FS_08) to equal the business unit that you are creating. You should not change this definition.

See "Planning Records, Control Tables, and TableSets" topic in the *PeopleTools: PeopleSoft Application Designer Developer's Guide*

See "Sharing Trees Across SetIDs" topic in the *PeopleTools: PeopleSoft Tree Manager*

Asset Management Business Unit Default Hierarchies and Options

A business unit is the highest level in the hierarchy and you must set default values for business units. All other entities fall beneath them in the hierarchy. Some of the attributes set at the business unit level may be set at lower levels in the hierarchy, such as the customer or item level, but are not required.

Default hierarchies exist throughout the system. Any time that a default hierarchy exists, you can:

- Leave information blank at lower levels, because defaults are inherited from the next higher level.
- Override information set at higher levels by entering different information at the lower levels.

Some business processes in Asset Management are based on your business unit definitions. These processes may require that you define field entries to be used by default or other options for transactions that are processed at the business unit level. These options include:

- Asset Management processing options.

Besides asset management processing defaults, you should consider your requirements for value-added tax (VAT) processing, processing group assets and ChartField summarization, depreciation period end and closing processes, and asset book and accounting entry defaults.

- (JPN) Asset Management numerical rounding options.

Define the rounding type for depreciation amounts.

- Payables interface processing options.

Select voucher close transaction types and lease payment options.

- Purchasing interface processing options.

Select the map ChartField option to assign the ChartFields that come to assets from a different ChartField value by using the criteria established on the ChartField Mapping Template page.

- Billing interface options.

Designate the defaulting business unit to run the Billing interface and define values for Billing business units, bill types, bill sources, and bill by identifiers.

- Real Estate Management (space allocation) interface options.

Designate the defaulting tree name, statistics code and statistical accounts to be used when interfacing with Real Estate Management.

- Maintenance Management interface options.

Designate the default options enabling retirements and transfer in or out of assets from work orders. Designate the default options for including or excluding subcomponents for transactions coming from MM.

If you are using PeopleSoft General Ledger, you must also define at least one general ledger business unit to which you will generate journal entries from the asset management business unit. If PeopleSoft General Ledger is already implemented, this step may have already been performed.

You can override most business unit defaults at a lower level when you enter asset information. Asset Management is delivered with a series of standard definition tables. Examine these tables to determine if the business unit that you are setting up can share the same financial structure. If so, you can minimize the need to set up additional tables.

VAT Processing

Value-added tax (VAT) defaults are controlled by VAT drivers at various levels of the hierarchy and the VAT defaults themselves are stored in a common set of defaulting tables. Depending on the driver, certain fields are available for setting and, lower in the hierarchy, overriding. There are two main components that control the VAT defaulting: the VAT Defaults Setup component and the Services VAT Treatment Setup component. Asset Management only handles goods for VAT setup. You can access these components from the common VAT menu (Set Up Financials/Supply Chain, Common Definition, VAT and Intrastat, Value Added Tax) or from the applicable application pages. If you access these components from the VAT menu, the driver you select determines the fields that display. If you access either of these components from the application pages, the component you are accessing from determines the fields displayed. The VAT Defaults Setup and Services VAT Treatment Drivers Setup components and functionality are described in depth in the common VAT topic in the *PeopleSoft Global Options and Reports* product documentation.

The values selected here become the default values for the business unit and can be overridden in the Asset Retirements component. If you leave these fields blank, you must enter this information in the Asset Retirements component each time VAT applies to the transaction.

Use the VAT Default page to specify VAT processing options. For countries that use VAT, PeopleSoft Asset Management stores default information at the business unit, customer, customer location, and asset class levels to calculate VAT on asset retirements. VAT transaction types and VAT codes are set up in Set Up Financials/Supply Chain, Common Definitions, VAT and Intrastat, Value Added Tax. You can select values for these and other control fields on this page.

See "Understanding VAT (*PeopleSoft FSCM 9.2: Global Options and Reports*)".

Cash Generating Units

Cash generating units (CGUs) become important when you must perform impairment assessment and processing for an individual asset and the recoverable amount of that asset is in doubt. If an organization cannot determine recoverable value for an individual asset, it is required in some countries to identify the lowest aggregation of assets that generate largely independent cash flows. These aggregations of assets are known as *cash generating units*. A CGU is the smallest identifiable group of assets that generate cash inflows from continuing use and are largely independent of the cash inflows from other assets or groups of assets and should be defined consistently from period to period.

PeopleSoft supports the implementation of International Accounting Standards (IAS) 36 by providing for the definition of a Cash Generating Unit and enabling the association of CGUs with business units. This facilitates impairment processing within a defined business unit. You must define the business unit before it can be associated to a CGU definition.

See "Adjusting for Asset Impairment (*PeopleSoft FSCM 9.2: Asset Management*)".

Creating PeopleSoft Asset Management Business Units

To set up business units, use the Business Unit Definition component (BU_DEFN).

This topic describes how to set up Business Units.

Pages Used to Create PeopleSoft Asset Management Business Units

Page Name	Definition Name	Navigation	Usage
AM Business Unit Definition	BUS_UNIT_TBL_AM	Set Up Financials/Supply Chain Management, Business Unit Related, Asset Management, Asset Management Definition, AM Business Unit Definition AM Business Unit Definition page	Create an asset management business unit and specify its default processing options.
Open Period Update	OPEN_PERIOD_SINGLE	Click Update Open Periods on the AM Business Unit Definition page.Open Period Update page	Define in which periods transactions can be posted for Asset Management.
Warehouse Mapping	AM_WAREHOUSE_MAP	Click Warehouse Mapping on the AM Business Unit Definition page.Warehouse Mapping page	Establish the default ChartField mapping rules necessary to accommodate asset component changeout transfers for this business unit.
VAT Defaults Setup	VAT_DEFAULTS_DTL	Click VAT Default on the AM Business Unit Definition page. VAT Defaults Setup page	Specify VAT Defaults Setup.

Page Name	Definition Name	Navigation	Usage
Copy VAT Defaults From	VAT_DFLT_SRCH_COPY	Click Copy Defaults From on the VAT Defaults Setup page. VAT Defaults Copy page	Copy VAT default specifications from another key combination for the same VAT driver.
Business Unit/Book Definition	BU_BOOK_DEFN_01	Set Up Financials/Supply Chain Management, Business Unit Related, Asset Management, Asset Management Definition, Business Unit/Book Definition Business Unit/Book Definition page	Define required books, book options, and accounting entry options for each book that the business unit will use. You must first complete the AM Business Unit Definition page and define your asset books on the Asset Book page.
Round Options	ROUND_OPTIONS_SEC	Click Round Type on the Business Unit/Book Definition page.	(JPN) Select options for rounding depreciation amounts for the book.
Depreciation Close List	MR_AM_DEPR_CLOS	Click Depreciation Close List on the Business Unit/Book Definition page.	Review the years and periods for which depreciation has been closed.
Business Unit Info for Japan	BUS_UNIT_JPN_SEC	Click the JPN Info link from the AM Business Unit Definition component.	Select the options to process tax and depreciation for Japan. To activate the JPN Info link, you must first specify JPN as the Localization Country within User Preferences - Overall page Set Up Financials/Supply Chain, Common Definitions, User Preferences, Define User Preferences, Overall Preferences.
Business Unit/Book Feature	BU_BOOK_FEATURE	Set Up Financials/Supply Chain, Business Unit Related, Asset Management, Asset Management Definition, Business Unit/Book Feature	Enable book and book options and (optionally) impairment and revaluation options for a business unit.
BU Book ChartFields Summarize	BU_BOOK_GRP_SUM	Select the Group Asset Processing check box on the Business Unit/Book Definition page.	(Optional) Select the ChartFields that will be used for group member asset summarization.

Page Name	Definition Name	Navigation	Usage
Interface Options	BUS_UNIT_INTFC_OPT	Set Up Financials/Supply Chain, Business Unit Related, Asset Management, Asset Management Definition, Interface Options Interface Options page	<p>Establish product and application interface default processing options for Payables, Purchasing, Billing, Real Estate Management, and Maintenance Management</p> <p>You must enable all PeopleSoft products you want to integrate with on the Installation Options page (INSTALLATION) before integration options will be available within the Business Unit component (BU_DEFN).</p>

Prerequisites

Before you set up business units, you must decide on your TableSet structure and set up SetIDs.

See "Planning Records, Control Tables, and TableSets" section in the *PeopleTools: PeopleSoft Application Designer Developer's Guide*.

AM Business Unit Definition Page

Use the AM Business Unit Definition page (BUS_UNIT_TBL_AM) to create an asset management business unit and specify its default processing options.

Navigation

Set Up Financials/Supply Chain Management, Business Unit Related, Asset Management, Asset Management Definition, AM Business Unit Definition.

Image: AM Business Unit Definition page

This example illustrates the fields and controls on the AM Business Unit Definition page. You can find definitions for the fields and controls later on this page.

Note: When you create a business unit, PeopleSoft Asset Management automatically defines TableSet defaulting for the business unit so that it copies the TableSet that you entered on this page. You can verify TableSet sharing by using the PeopleTools Utilities TableSet Control Group pages.

See "Planning Records, Control Tables, and TableSets" section in the *PeopleTools: PeopleSoft Application Designer Developer's Guide*

Unit, Description, and Short Description

Enter descriptive information to uniquely identify the business unit during set up. These fields are already populated when you select an existing business unit for update.

Business Unit Definition

Define the book to be used as the default book for general ledger entries for the business unit and all secondary books, including Corporate and Tax books (both state and federal).

Location

Select a location for this business unit. Locations available are defined on the location page table.

Last Asset ID Used

The last asset ID used displays here or the value is zero by default. To increment automatically from some other starting point, enter your starting point into the Last Asset ID Used field

and click the Reset button. If there are no assets for this business unit, this will reset the last asset ID to zero. The *Next* value displays on the Asset Basic Add, Operational Asset Definition or Express Add pages when you use automatic numbering of asset ID. When the record is saved, the assigned asset ID displays and the value is incremented on this page.

Default Book

Select the book that is used by default when you enter assets. (This book is required for subsequent processing.)

Note: PeopleSoft strongly recommends making the primary book in the ledger group in PeopleSoft General Ledger the same as the default book in PeopleSoft Asset Management in order to maximize synchronicity of transactions.

Fed Book (federal book)

Select the book to calculate the federal tax.

AMT Book (alternative minimum tax book) Select the book to calculate the alternate minimum tax.

ACE Book (adjusted current earnings book) Select the book to calculate the adjusted current earnings.

CAP Book (capital acquisition planning book) Select the book used for capital acquisition planning (CAP).

Lease Book Select the book where leased assets are primarily recorded.

Suspense Account and Alt Acct (alternate account) Enter the translate account and alternate account here. If you have any transactions in a foreign currency within this business unit and want to enable the feature to translate currencies. If you do not have transactions outside of your local currency, you do not need to define these values.

See "Defining Journal Processing Options for a Business Unit (*PeopleSoft FSCM 9.2: General Ledger*)".

BU Setup Options

Keep all books in synch

Select this check box to keep all adjustments synchronized. Deselecting this check box enables you to create adjusting entries to affect particular books while excluding others.

If you select this option in conjunction with a business unit that is also enabled for impairment and revaluation processing, you will have an option to create zero impairment and revaluation costs for other books. This occurs when working in the Impairment Worksheet page, the Revaluation Worksheet page, or the batch run control page and you select the Copy To Other Books check box.

	<p>Warning! If you use this method to make adjusting entries, you must reselect the option before starting normal asset processing. Deselecting or selecting this option does not enable retroactive adjustments. The function is applied from the point selected going forward until and unless you change it again.</p>
Default tag # from asset ID (default tag number from asset ID)	Select this check box to use the same number for the tag as the assigned asset ID.
Allow duplicate tag numbers	Select this check box when you are processing physical inventory. This enables you to take physical inventory and process assets that may have the same tag number.
Joint Venture Unit	Select if this is a joint venture business unit.
	<hr/> <p>Note: You cannot perform interunit transfers on joint venture business units.</p> <hr/>
Use JV Participant Bk Profile (use joint venture participant book profile)	Select this option for participant level. Joint venture participant business units are governed by the book for the <i>participant</i> level business unit or by the book for the overall joint venture business unit. You can use this feature to maintain joint venture participant business units with separate profiles that enable different depreciation methods, conventions, calculation types, and so on, as required.
Use Parent-Child Defaulting	Select to enable automatic parent-child inheritance processing for this business unit. For example, when you create a child asset and you want it to inherit the tag or department number from the parent asset (as specified on the Profile Child Asset Inheritance page), select this check box. For more responsive performance of Express Add, Basic Add, and Transaction Loader processes, deselect this check box. General parent-child asset processing is still enabled.
Auto-Retire Fully Depr Assets (automatically retire fully depreciated assets)	Select to enable automatic retirement of fully depreciated assets for this business unit. You must also enable the option at the book level.
Use Add Conv. for all TXNs (use add convention for all transactions)	Select this option to inherit the same convention used when you added an asset for any new transaction.
Use Cap Threshold (use capitalization threshold)	Select to enable Capitalization Threshold processing at the business unit level. You must also enable the Capitalization Threshold feature at the system level from Installation Options.
	See Capitalization Thresholds Page .
Use ARO (asset retirement obligation)	Select this option to enable asset retirement obligation (ARO) processing for the asset business unit. Then, upon creating an asset, you designate it as an ARO-eligible asset within the Basic Add component. This functionality provides asset retirement obligation measurement and reporting in compliance with Financial Accounting Standards for leased assets, group assets,

and asset impairment. You can enable ARO processing at the asset profile level, the business unit level, and the asset level.

When you select this option, the Include ARC in Impairment Test, ARO Prefix, and Last ARO Id fields appear.

ARO Prefix (asset retirement obligation prefix)

Enter a prefix to be used for accounting entries that are related to asset retirement obligations. The prefix is for the asset ID that will be created to store the ARO Information (ARO-eligible asset).

Last ARO Id (last asset retirement obligation Id)

Specify the numerical value after which the count should be added for each subsequent ARO ID. This works in combination with the prefix. Suppose the prefix is "ARO", when you start using the feature, the Last ARO Id will be zero. Since Asset ID has 8 characters, the first ARO created will be ARO00001.

Include ARC in Impairment Test (include asset retirement cost in impairment test)

This option appears if you have selected the *Use ARO* field. Select this check box to include the asset retirement cost in the impairment process calculation.

For more information, see "Accounting for Asset Retirement Obligations (*PeopleSoft FSCM 9.2: Asset Management*)"

InterUnit Transfer Defaults Options

Select the default asset information to be shared between the business units when you make interunit transfers. The information is derived from the Asset Information component. The selections made here are the default options for the Asset Cost IU (interunit) Transfer (ASSET_COST_02) page.

Asset Acquisition Info

Select to include information derived from the Asset Acquisition Detail (ASSET_ACQ_DETAIL) page and links (ASSET_ACQ_DET_AP, ASSET_ACQ_DET_VAT).

Asset Attributes Info

Select to include information derived from the Asset Location/Comments/Attributes (ASSET_IMAGE) page.

Asset License/Register Info

Select to include information derived from the Asset Custodian/License/Manufacturer page (ASSET_CUSTODIAN) and links (ASSET_LIC_ADDR_SEC).

Asset Lease Info

Select to include information derived from the Leased Assets component pages (ASSET_LEASE_01, ASSET_LEASE_02, ASSET_LEASE_05, ASSET_LEASE_03).

Asset Non-Capitalized Cost

Select to include information derived from the Asset Acquisition Detail (ASSET_ACQ_DETAIL) page and links (ASSET_ACQ_DET_AP, ASSET_ACQ_DET_VAT).

Asset Maintenance Info

Select to include information derived from the Track Service and Repairs component pages (ASSET_MAINT_01, ASSET_MAINT_01_S) and meter readings.

Asset Comments

Select to include information derived from the Asset Location/Comments/Attributes (ASSET_IMAGE) page.

Asset Warranty Info	Select to include information derived from the Asset Custodian/License/Manufacturer page (ASSET_CUSTODIAN) and links (ASSET_WARRANTY).
Asset Insurance Info	Select to include information derived from the Asset Custodian/License/Manufacturer page (ASSET_CUSTODIAN) and links (ASSET_INSURANCE).
Asset Inspection Info	Select to include information derived from the Asset Custodian/License/Manufacturer page (ASSET_CUSTODIAN) and links (ASSET_INSPECTION).
Asset Component History	Select to include asset component history (AM_AST_COMP_HIST) information.
Asset Attribute Groups Info	Select to include asset attribute groups (AM_ASSET_SD) information.

Open Transaction Processing Options

Open transactions are asset events such as depreciation and accounting entries that require processing. PeopleSoft Asset Management assigns each open transaction a unique open transaction ID whenever a processing option is requested. For example, changing asset cost, adding or retiring assets, or changing asset depreciation attributes all create open transactions. Depreciation must be calculated, or recalculated, and allocated for each transaction before it is considered closed. An open transaction has a *Pending* status until it is processed.

Auto Increment Open Trans ID (automatically increment open transaction ID) If you want to process a large number of transactions as a group, you should deselect the Auto Increment Open Trans ID check box. For example, you enter 300 new computers into PeopleSoft Asset Management, and rather than process depreciation and distribution in 300 separate requests, you want to process all in a single request. To do so, establish an open transaction ID that identifies a single processing request for all 300 computers that you entered. In this case, you should deselect the Auto Increment Open Trans ID check box.

Open Trans ID (open transaction ID) The Open Trans ID field helps you keep track of open transaction processing status. You can enter a beginning open trans ID, or you can have PeopleSoft Asset Management assign it. You can specify that PeopleSoft Asset Management automatically increment the ID value each time a transaction is added to the open transaction table by selecting Auto Increment Open Trans ID. The next processing request that you enter is automatically assigned a number that is one greater than the last assigned value. Subsequent open transaction ID numbers will be incremented by one.

Related Links

"Understanding General Ledger Business Units and Options (*PeopleSoft FSCM 9.2: General Ledger*)"

"Setting Up Financials Audit Framework (Audit Logging) (*PeopleSoft FSCM 9.2: Application Fundamentals*)"

"Setting Up Cross-Application Installation Options (*PeopleSoft FSCM 9.2: Application Fundamentals*)"
[Understanding Asset Processing](#)

"Understanding Asset Information Flow (*PeopleSoft FSCM 9.2: Asset Management*)"

Open Period Update Page

Use the Open Period Update page (OPEN_PERIOD_SINGLE) to define in which periods transactions can be posted for Asset Management.

Navigation

Click Update Open Periods on the AM Business Unit Definition page. Open Period Update page

Image: Open_Period_Update page

This example illustrates the fields and controls on the Open Period Update page. You can find definitions for the fields and controls later on this page.

From Year	From Period	Begin Lag	First Open	To Year	To Period	End Lag	Last Open
1998	1	0	04/01/1998	2019	12	0	03/31/2020

The Update Open Periods page enables you to define which periods are open (periods in which transactions can be posted) for PeopleSoft Asset Management. These can be defined in relation to, but not strictly governed by, the corresponding open period in General Ledger (GL).

Related Links

"Defining and Updating Open Periods and Adjustment Periods (*PeopleSoft FSCM 9.2: Application Fundamentals*)"

VAT Defaults Setup Page

Use the VAT Defaults Setup page (VAT_DEFAULTS_DTL) to specify VAT Defaults Setup.

Navigation

Click VAT Default on the AM Business Unit Definition page. VAT Defaults Setup page

This section provides an overview of VAT processing options and describes how to set up VAT processing defaults by business unit for PeopleSoft Asset Management.

Understanding VAT Drivers, VAT Driver Keys, and the Defaulting Hierarchy for VAT Defaults

The following table lists the PeopleSoft Asset Management-related VAT drivers and associated VAT driver keys in VAT default hierarchy sequence from most specific to least specific for the VAT Defaults component. The table also indicates which drivers control defaults for the Services VAT Treatment:

VAT Driver	VAT Driver Keys	Country	State	Applicable to Regular VAT Defaults	Applicable to Services VAT Treatment Defaults
ASSET_CLASS_TBL Asset Class	Asset SetID Asset Class	Optional	Optional	Yes	No
CUST_ADDR_SEQ Customer Location	Customer SetID Customer ID Address Sequence Number	Optional	Optional	Yes	Yes
CUSTOMER Customer	Customer SetID Customer ID	Optional	Optional	Yes	Yes
BUS_UNIT_TBL_AM AM Business Unit	Business Unit	Optional	Optional	Yes	No
VAT Entity Registration	VAT Entity Country	Not applicable	Optional	Yes	No
VAT Country	Country	Not applicable	Optional	Yes	No

Establishing the VAT Environment

For your system to track and process VAT, you must first set up basic information by defining VAT transaction types, VAT codes, and their associated VAT accounting templates, VAT countries, VAT entities, and VAT defaulting. Each piece builds upon the next; therefore, for your basic setup, it is important to implement each piece in the following order:

1. VAT transaction types.
2. VAT rates, VAT codes, and VAT accounting information.
3. VAT countries.
4. VAT entities.

5. VAT defaults.

In addition to the information you must set up, PeopleSoft delivers multiple account types for your VAT accounting and reporting with every application. You cannot add your own.

See "Understanding VAT (*PeopleSoft FSCM 9.2: Global Options and Reports*)".

VAT Defaults Setup Page

Image: VAT Defaults Setup Page

This example illustrates the fields and controls on the VAT Defaults Setup Page. You can find definitions for the fields and controls later on this page.

Specify the VAT driver and any VAT driver keys as applicable. You can insert rows for any or all of the VAT driver keys as well as the VAT country or state. You can also delete any existing rows.

Copy Values to New Rows

If you are inserting a row for a VAT driver key, select this check box to copy all the VAT defaults from the previous row to the

new row. Otherwise, all VAT default fields for the new row will be blank.

VAT Defaults

VAT Reporting Country

Select the VAT reporting country or countries for which you are defining VAT defaults. For service VAT treatment defaults, defaults are obtained for the supplier's location country. PeopleSoft Asset Management *does not* use VAT for services, only goods.

Defaulting State

As applicable, enter the state for which you want to define defaulting values. (Optional depending on VAT Country)

Copying VAT Defaults

Access the VAT Defaults Copy page (Click Copy Defaults From on the VAT Defaults Setup page.

Copy From Search Criteria

Enter the criteria on which you want to search. When copying defaults for the PeopleSoft Asset Management business unit driver, you can search by business unit, VAT reporting country, and defaulting state.

Search

Select to retrieve the results based on the criteria entered. The results display in the Copy From Results group box.

Copy From Results

In the Copy From Results group box, select the link for any of the results returned to view the details of the VAT setup from which to copy on the Copy VAT Defaults Setup page. Once you have viewed the details, you can select Copy to copy the VAT setup. The system returns you to the VAT Defaults Setup page with the copied fields.

Or you can select the appropriate option for any of the results returned and select Copy to copy from the selected row. The system returns you to the VAT Defaults Setup page with the copied fields.

Default Details

Enter the effective date and status.

The remaining fields on the page vary based on the combination of VAT driver and VAT driver keys. Depending on the combination of PeopleSoft products you are implementing and the VAT transactions conducted between your local country and other countries, you may require some variation in set up. The *PeopleSoft Global Options and Reports* product documentation explains these variations in working with VAT in greater detail.

You may define the following defaults for the PeopleSoft Asset Management business unit:

See "Establishing VAT Defaults (*PeopleSoft FSCM 9.2: Global Options and Reports*)".

VAT Control Defaults

VAT Applicable	Select the appropriate VAT status. Values are: <i>Exempt</i> (not subject to VAT) <i>Outside of Scope of VAT</i> <i>Taxable</i>
Goods Declaration Point	Select when you want VAT transaction information for goods to be recognized for reporting purposes. Values are: <i>At Accounting Date</i> : VAT is recognized at the accounting date. <i>At Delivery Time</i> : VAT is recognized at time of delivery. <i>At Invoice Time</i> : VAT is recognized at time of invoice. <i>At Payment Time</i> : VAT is recognized at time of payment.
Calculation Type	Select the type of calculation you want the system to use. Values are: <i>Exclusive</i> : VAT is calculated on top of the entered transaction amount, because it excludes any VAT. <i>Inclusive</i> : VAT is calculated from within the entered transaction amount, because it already includes the VAT.
(UK) Domestic Reverse Charge	Select <i>Yes</i> to enable the domestic reverse charge default at the business unit level. This default indicates that the goods on transaction lines associated with the VAT Driver are domestic reverse charge goods. See "Establishing VAT Defaults (<i>PeopleSoft FSCM 9.2: Global Options and Reports</i>)".

VAT Code Defaults

You use VAT codes to specify the rate at which VAT is calculated.

The VAT rate is frequently the key to reporting VAT because VAT amounts must often be reported separately by VAT rate on a VAT return. Therefore, the VAT code is part of the reporting definition.

Taxable Goods Sales	Select the VAT code to be used for taxable sales within this VAT reporting country
----------------------------	------------------------------------------------------------------------------------

See "Setting Up VAT Authorities, and Tax Codes (*PeopleSoft FSCM 9.2: Global Options and Reports*)".

VAT Transaction Type Defaults

You use VAT transaction types to classify and categorize transactions at a more detailed level for both VAT reporting and accounting. These are specified for each transaction line when you enter a transaction.

You define the VAT transaction types you need for your VAT setup. PeopleSoft also delivers a set of VAT transaction types with your system as sample data.

Domestic Reverse Charge Sales	Select the transaction type default to be used for domestic reverse charge sales. See "Establishing VAT Defaults (<i>PeopleSoft FSCM 9.2: Global Options and Reports</i>)".
Domestic Goods Sales	Sale of goods within the same country.
EU Goods Distance Sales (European Union goods distance sales)	Sale of goods between European Union (EU) countries in which the supplier is registered in an EU country and the purchaser is not registered in an EU country. The VAT rate charged is the rate applicable in the supplier's country.
EU Goods Sales (European Union goods sales)	Sale of goods within the European Union.
EU Sales, Simplification	This treatment is used for the transaction between an intermediary and the purchaser in cases when there is a sale of goods between European Union (EU) countries involving three parties: the purchaser, an intermediary (bill-from) supplier, and the actual goods supplier. Each party is located in a different EU country and registered in his own country, and not in either of the other two countries. The only difference between this VAT treatment and that applied to normal EU sales is that the supplier is required to print a different message on the invoice referencing the statute that applies to triangulation, rather than the one that references the statute for normal EU sales.
Exempt	Not subject to VAT.
Exonerated	Subject to exoneration from VAT.
Goods Exports	Export sales of goods.
Out of Scope	Outside of the scope of VAT.
Suspended	Subject to suspension of VAT.

See "Defining VAT Transaction Types (*PeopleSoft FSCM 9.2: Global Options and Reports*)".

Business Unit info for Japan Page

Use the Business Unit Info for Japan page (BUS_UNIT_JPN_SEC) to Select the options to process tax and depreciation for Japan.

Navigation

Click the JPN Info link from the AM Business Unit Definition component.

The JPN Info (Japan information) link appears on the AM Business Unit Definition page when you set up the overall options for user preferences (OPR_DEF_TABLE_FS1) in the Common Definitions component: Set the Localization Country value to JPN (Japan).

Image: Business Unit info for Japan page

This example illustrates the fields and controls on the Business Unit info for Japan page. You can find definitions for the fields and controls later on this page.

Corporate Book for Japan

Select the corporate book for Japan.

Tax Book for Japan

Select the tax book for Japan.

Note: PeopleSoft recommends that you select the primary book in the ledger group in PeopleSoft General Ledger to be the same as the default book in PeopleSoft Asset Management. As tax books do not usually send accounting entries to PeopleSoft General Ledger this maximizes synchronicity of transactions.

Memorandum Amount and Currency

Enter the memorandum amount at the end of the useful life of the asset as required by the Japanese tax regulation. This value is used in conjunction with the following depreciation methods:

- Japan - Tangible Declining Balance with Straight Line Switch
- Japan - Tangible Straight Line
- Japan - Extended Straight Line

The memorandum amount reflects the currency of the tax book for Japan as the default. For books that use one of the aforementioned depreciation methods in a currency other than JPY, the memorandum amount is translated to the respective book's currency. The memorandum value is established for each asset management business unit.

Advanced Depreciation

Select if advanced depreciation is used.

Japan Composite

Select if composite assets are used.

Use JPN Local Tax

Select if local tax reporting is enabled.

Related Links

"(JPN) Using PeopleSoft Asset Management Options to Meet Japanese Requirements (*PeopleSoft FSCM 9.2: Asset Management*)"

Business Unit/Book Definition Page

Use the Business Unit/Book Definition page (BU_BOOK_DEFN_01) to define required books, book options, and accounting entry options for each book that the business unit will use.

Navigation

Set Up Financials/Supply Chain Management, Business Unit Related, Asset Management, Asset Management Definition, Business Unit/Book Definition

Image: Business Unit/Book Definition page

This example illustrates the fields and controls on the Business Unit/Book Definition page. You can find definitions for the fields and controls later on this page.

The screenshot displays the 'Business Unit/Book Definition' page for Unit JPN01. The 'Book' section includes 'Book Name' (CORP_USD) and 'Book Type' (Corporate Book). The 'Book Options' section includes 'Currency' (USD), 'Rate Type' (CRRNT), 'Calendar' (J1), and 'Capitalize Limit' (Amount). The 'Accounting Entry Options' section includes 'Create Accounting Entries' (checked), 'GL Business Unit' (JPN01), 'Ledger Group' (RECORDING), 'Budget Ledger Group', 'Account Entry Template ID' (DEFAULT), 'Statutory Book', 'Ledger' (CORPORATE), and 'Budget Ledger'. The 'Chartfield Edit Option' section includes 'No Edits' (selected), 'Warning', and 'Reject w/ edit error'. A 'Comment' field is at the bottom.

Book Name

The Book Name field is used during asset and profile entry to designate book processing.

At least one financial book for each business unit to record asset data in the general ledger is required. You may have other federal, state, and foreign tax or financial books as

well. Transactions can be tracked in multiple currencies by designating the currency code within each transaction entry.

Note: If there is a need to add books to an existing business unit once assets have been added, you should use the Add/Copy Asset Book feature to avoid possible impact to existing assets in the business unit.

Book Type

Specify the type of asset book processing. This feature acts as a filter for tax and financial options when you define tax and depreciation information for asset transactions. For example, if you define the CORP book as a *Corporate* book, you will not be able to select any tax attributes for processing when you add an asset to this book. Select *Corporate w/Tax Info* if you maintain separate tax records for this business unit in the book. You can use this option to specify tax processing rules and track tax information for your assets. The *Tax* option enables you to maintain tax information for government reporting. The *US AMT* option enables you to maintain alternative minimum tax information for government reporting. This option enables you to separately track alternative minimum tax information.

Book is Required

Select Book is Required to ensure that this book will added for every asset in this business unit.

Note: If you maintain multiple currencies you must define the exchange rate. Even if you use only one currency in PeopleSoft Asset Management, you must still set up a one-to-one exchange rate and rate type to exchange that currency with itself. For example, to use U.S. dollars you must set up an exchange rate for U.S. dollars to U.S. dollars with an exchange rate of 1. To make changes, go to Set Up Financials/ Supply Chain, Common Definitions, Market Rates page.

See "Understanding Foreign Currency Processing (*PeopleSoft FSCM 9.2: Global Options and Reports*)".

Book Options

Currency

Displays the default currency for this business unit.

Rate Type

Select the currency exchange rate.

Note: Even if you are using only one currency in PeopleSoft Asset Management, you still need to set up a one-to-one exchange rate and rate type to exchange that currency with itself. For example, to use US Dollars you must set up an exchange rate for USD to USD with an exchange rate of 1.

See "Understanding Foreign Currency Processing (*PeopleSoft FSCM 9.2: Global Options and Reports*)".

Calendar

Select the accounting period calendar for this book and business units. General Ledger supports multiple calendars, so you can keep separate calendars for actual accounting activity, for budget and forecast activity, and for special reporting

or transitional needs. For example, you can easily manage a conversion to different accounting periods or to a new fiscal year by maintaining two calendars. However, only one calendar can be active for a ledger group at a given time. A book must use the same calendar as the ledger.

See "Understanding Accounting Calendars Based on Open and Close Periods (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

Capitalize Limit, Amount, and Limit Code Define these limits either by selecting Amount and entering a minimum, or by selecting *Table Lim* and selecting a Cost Limit Code. If you select Amount, you cannot add an asset with a cost that is less than the specified limit. If you select Table Lim, you may encounter an error or a warning, based on the actions that you set up in the Capitalization Limit table, when you try to add assets below the amounts in the table.

See [Capitalization Limits Page](#).

Lease Cap Min (lease capitalization minimum) Define the lease cap as a minimum cost of the asset lease. (When you enter a leased asset with total cost below the lease cap, you will receive an error.)

Accounting Entry Options

Your business unit accounting entry options enable you to associate an asset management business unit with a general ledger business unit and default ledger.

Create Accounting Entries Select this check box to make the accounting entry options available for selection.

Retirements by Disposal Code Select the check box to enable retirement of assets based upon disposal code. The Transaction Code field on the Retirement page will be populated with the appropriate disposal code.

See "Initiating Asset Retirement Using the Disposal Worksheet (*PeopleSoft FSCM 9.2: Asset Management*)".

Translate Gain/Loss If the ledger specified is a translate ledger, this check box appears. When you process accounting entries (AM_ AMAEDIST), the gain or loss amount that is the result of a currency exchange transaction is converted from the primary book to the translate book.

GL Business Unit The General Ledger business unit associated with this book displays here.

Ledger Group, Budget Ledger Group, Ledger, and Budget Ledger A ledger is a set of posted balances that represents a set of books for a business unit. Ledger templates and detail ledgers can be added to the appropriate ledger group. A ledger group can have one primary ledger and zero to nine secondary ledgers. Each ledger within the ledger group shares a common physical

structure based on the ledger template, as well as unique characteristics (such as its own base currency).

The Ledger Group and Budget Ledger Group fields for PeopleSoft Asset Management enable you to associate a ledger or ledger group to this business unit. *In sync* accounting entries are a group of accounting entries for one transaction that the system distributes to different ledgers. In conjunction with the Keep all books in sync option, you define how a transaction is posted. If the Keep all books in sync option is selected, then one transaction will post to all ledgers in the group. If the Keep all books in sync option is deselected, the system posts transactions only to those ledgers with transaction entries. One book will post to one ledger, but you can set up other books to point to the other ledgers in the group.

If you will be generating budget accounting entries, specify the Budget Ledger Group and Budget Ledger to which you want to post them. If you leave ledger and budget ledger fields blank, the accounting entries will be made to the primary ledger.

See "Understanding Ledgers (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

Book Code Distrib. Grp (book code distribution group)

If the *Book Code* option is activated from the Installation Options page, this field appears. The book code is an *Account* attribute and a balancing *ChartField*. You can use book codes to simultaneously generate sets of entries to record related transactions according to multiple GAAPs for the same business unit in the same ledger.

The book code distribution group defines a set of book codes to be used when distributing accounting entries for multiple GAAPs within one book. Using the book code distribution group restricts the duplication of accounting entries being passed to General Ledger. The book code distribution group value is defined on the Book Code Distribution Group page.

Select from the available book code distribution groups defined for your organization.

See "Setting Up Application-Specific Installation Options (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

See [Creating PeopleSoft Asset Management Business Units](#).

See [Understanding Accounting Entry and Financial Processing](#).

See "Adding Book Code Values (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

Account Entry Template ID

Enter the account entry template ID. The accounting entry template ID provides the option to associate different books with different charts of accounts. To use derogatory depreciation for France, select the account entry template

ID that corresponds. You must also select the Derogatory Depreciation check box.

See [Defining Accounting Entries](#).

(FRA) Derogatory Depreciation

Select this check box to process derogatory depreciation with the derogatory account entry template ID. If this box is selected, you must use the appropriate account entry template ID associated with derogatory depreciation. You must also select the statutory book to which this book will be compared. This can be designated on the AM Business Unit Definition page as the federal book.

See "(FRA) Using PeopleSoft Asset Management Options to Meet French Requirements (*PeopleSoft FSCM 9.2: Asset Management*)".

(FRA) Statutory Book

Select the statutory book to which derogatory depreciation transactions stored in the book you are defining will be compared. When Derogatory Depreciation has been selected, you must also define statutory book.

ChartField Edit Options

Select the ChartField combination editing option default at the business unit level for Asset Management. Choose one of the following options:

- No Edit: No ChartField combination editing is performed.
- Warning: A warning is issued for ChartField combination editing errors. You can save online transactions with ChartField combination errors, correct the errors, or process the transaction with warning. The batch process loads transactions that fail with warning edits. A message is included in the Process Scheduler Message Log.
- Reject: Transactions that do not pass ChartField combination editing are rejected from processing until the error is corrected.

Round Options Page

Use the Round Options page (ROUND_OPTIONS_SEC) to (JPN) Select options for rounding depreciation amounts for the book.

Navigation

Click Round Type on the Business Unit/Book Definition page.

Round Rule and Round Type

Select the rounding rule and type that apply to this book.

The rounding rules delivered with PeopleSoft Asset Management are:

Down

Nat Rnd

Up

The rounding types delivered with PeopleSoft Asset Management are:

Currency:

Generic

Round Precision

The number of places to the right or left of the decimal point to which the amount or number will be rounded. If you select *Currency* as the round type, the system automatically determines round precision from the currency code.

Rounding Factor

The number to which the amount will be rounded. For example, if you select *Nat Rnd* as the rounding rule and enter a rounding factor of 25, amounts will be rounded to the nearest multiple of 25; for example, an amount of 130 will be rounded to 125, and an amount of 140 will be rounded to 150. If you select *Currency* as the round type, the system will automatically determine the rounding factor from the currency code.

Truncation Precision Flag

The Truncation Precision Flag check box works with the round precision value. When you select it, amounts that contain many decimal places are truncated to one decimal place to the right of the rounding precision position before rounding is performed.

If you deselect it, the entire amount is rounded. This example illustrates truncation precision:

- Amount to be rounded: 10.03439
- Round Precision: 3

With the Truncation Precision Flag check box selected, the system truncates the fifth decimal place and rounds 10.0343.

With the check box deselected, the system rounds the entire amount. Actual rounding results would depend on the selected rounding rule and round type.

Depreciation Close List Page

Use the Depreciation Close List page (MR_AM_DEPR_CLOS) to Review the years and periods for which depreciation has been closed.

Navigation

Click Depreciation Close List on the Business Unit/Book Definition page.

View the years and periods for which depreciation has been closed. You cannot open or close periods from this page.

Related Links

"Clearing Reconciliation Page (*PeopleSoft FSCM 9.2: Asset Management*)"

Business Unit/Book Feature Page

Use the Business Unit/Book Feature page (BU_BOOK_FEATURE) to enable book and book options and (optionally) impairment and revaluation options for a business unit.

Navigation

Set Up Financials/Supply Chain, Business Unit Related, Asset Management, Asset Management Definition, Business Unit/Book Feature

Image: Business Unit/Book Feature page

This example illustrates the fields and controls on the Business Unit/Book Feature page. You can find definitions for the fields and controls later on this page.

This page provides the book, impairment and revaluation options available for the books that have been defined within this business unit definition. The Impairment/Revaluation Options group box displays only when Impairment Processing and Revaluation Processing are selected on the Installation Options page for Asset Management.

See "Installation Options - Asset Management Page (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

Book Options

(DEU) Low Value Asset

Select to enable low-value asset processing. In Germany, assets marked as low value should be depreciated in one year. PeopleSoft Asset Management checks the capitalization limits against the amounts that are stored by code in the capitalization limit table.

See "(DEU) Using PeopleSoft Asset Management Options to Meet German Requirements (*PeopleSoft FSCM 9.2: Asset Management*)".

Group Asset Processing

Select to enable group asset processing. If checked, the Summary link displays on the Chartfield Summarization page. The system applies asset transactions at the group member level.

Store Depr by Period (store depreciation by period)	<p>See "Understanding Group Asset Processing (<i>PeopleSoft FSCM 9.2: Asset Management</i>)".</p> <p>Select to store depreciation by period for the current fiscal year.</p> <hr/> <p>Note: If you store depreciation entries by period, you increase the table size and decrease depreciation processing performance. For optimal depreciation processing performance and greater table efficiency, we recommend storing depreciation entries by fiscal year rather than by period.</p> <hr/> <p>See "Understanding Interim and Year End Closing (<i>PeopleSoft FSCM 9.2: General Ledger</i>)".</p>
Child Inherits Parents Life	<p>Select to pass on the asset life of the parent asset to the child asset.</p>
Auto-Retire Fully Depr Assets (automatically retire fully depreciated assets)	<p>Select to enable the automatically retire fully depreciated assets feature. This field appears only if you select the Auto-Retire Full Depr Assets option on the Asset Management Business Unit Definition page.</p>
Online Reporting	<p>Select to enable online reporting features.</p> <hr/> <p>Note: You must run Load Depreciation Reporting process for at least one asset after this option is selected to be able to view online reporting for this business unit/book.</p> <hr/> <p>See "Understanding Asset Management Reporting Options (<i>PeopleSoft FSCM 9.2: Asset Management</i>)".</p>
(ARG, BRA, and MEX) Inflation Processing	<p>Select <i>Inflation Processing</i> if you want to enable the inflation processing feature. This optional feature is used for Argentina, Brazil, and Mexico to adjust assets for inflation associated with a particular inflation index appropriate for a country or currency. It provides for periodic inflation adjustment transactions (transaction type <i>INF</i>) that adjusts asset balances (cost, period depreciation, year-to-date depreciation, and accumulated depreciation) for inflation. The default is blank. (This field is available when you enable the corresponding installation options.)</p> <p>See Asset Profiles - Depreciation Page.</p>
Calculation Type	<p>This option appears when you select the <i>Inflation Processing</i> check box. Select the calculation method for inflation processing. The available options are:</p> <ul style="list-style-type: none"> • <i>Argentina</i> • <i>Brazil</i> • <i>Mexico</i>

See "Setting Up Cross-Application Installation Options (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

**Stop Depr when NBV < Salvage
(stop depreciation when net book
value is less than salvage value)**

Select to stop the depreciation calculation when the net book value of an asset is less than its salvage value. This is in compliance with International Accounting Standards. This field appears only if you select the Stop Depr when NBV < Salvage option on the Installation Options - Asset Management page.

Impairment/Revaluation Options

Impairment Process

Select this check box to enable impairment processing within this business unit book.

Cost Type For Impairment Loss

Select the default *Cost Type* for the impairment loss from the list of valid cost types.

Revaluation Method

Select the default method to be used for revaluation processing on the Revaluation Worksheet. The available options are:

- *Cost Based*
- *Dpr Wt-off* (depreciation write-off)
- *Inv Prop* (investment property)

Note: You can override this value on the Revaluation Worksheet.

Impairment Reversal

Select this check box to enable impairment reversal processing within this business unit book.

**Cost Type for Reval Reversal (cost
type for revaluation reversal)**

Select the default *Cost Type* for the impairment revaluation reversal from the list of valid cost types.

Revaluation Process

Select this check box to enable revaluation processing within this business unit book.

Cost Type for Revaluation

Select the default *Cost Type* for the revaluation process from the list of valid cost types. Cost Type for Revaluation must be defined if the Revaluation Process check box is selected.

Note: The Cost Type for all books in the same ledger group are automatically set as the same value as long as the keep ledgers in synch (KLS) option is enabled for the ledger group.

Revaluation Write-Off

Select to use this as the default revaluation method for the Revaluation Worksheet. If this check box is not selected at the business unit level, it is not available for selection at the Revaluation Worksheet level.

**Rev. Trans. Code: (revaluation
transaction code)**

Select the default *Transaction Code* for the revaluation process from the list of valid transaction codes. This is the transaction code to be used for the write-off of accumulated depreciation

and is required when the Revaluation Write-Off check box is selected.

Cost Type for Reval Write-Off

Select the default *Cost Type* for the revaluation write-off process from the list of valid cost types.

Note: The Cost Type for all books in the same ledger group will be automatically set as the same value.

Revaluation Reversal

Select to choose another Cost Type to deal with transactions where they decrease the amount of a prior impairment. In accordance with International Accounting Standards, you must first reverse any prior impairment loss before calculating the revaluation surplus.

Investment Property

Select to enable the Investment Property feature at the business unit level. This feature provides an easy way to identify Investment Property in compliance with International Accounting Standards. This check box appears only when the Revaluation process is activated on the Installation Options - Asset Management page.

See [Understanding Accounting Entry and Financial Processing](#).

Cost Type for Imp Reversal (cost type for impairment reversal)

Select the default *Cost Type* to track impairment reversals from the list of valid cost types.

Note: The Cost Type for all books in the same ledger group are automatically set as the same value. We strongly recommend that you do not change the cost types once they are established, because this may cause defective calculations.

Inv. Prop Trans Code (investment property transaction code)

Select the default *Transaction Code* from the list of valid transaction codes. This transaction code is to be used for processing investment property assets and is required when the Investment Property check box is selected.

Note: Only cost types selected for impairment and revaluation are visible from this page. Modifying the cost types after performing revaluations and impairments may cause inaccurate calculations in future revaluations or impairments. We strongly recommend that you do not change the cost types once transactions have been completed.

Interface Options Page

Use the Interface Options page (BUS_UNIT_INTFC_OPT) to establish product and application interface default processing options for Payables, Purchasing, Billing, Real Estate Management, and Maintenance Management

Navigation

Set Up Financials/Supply Chain, Business Unit Related, Asset Management, Asset Management Definition, Interface Options Interface Options page

Image: Interface Options page

This example illustrates the fields and controls on the Interface Options page. You can find definitions for the fields and controls later on this page.

This page provides the options available for interfacing with Payables, Purchasing, Billing, Real Estate Management (space management allocation), and Maintenance Management applications.

AP/PO Interface Options

Map ChartField

Select this check box to enable ChartField mapping for Payables and Purchasing asset processing.

Voucher Close Transaction Type

When a new asset is created from a PeopleSoft Payables voucher and sent to PeopleSoft Asset Management, a new asset is created. If the payables voucher is then closed you have to post the voucher again. The default Voucher Close Transaction is Retirement.

Note: If a voucher is unposted, and the default voucher close transaction is *Retirement*, the load type will result in a negative ADD (Load type *AAD*).

Negative Addition

Results in a negative addition (AAD) to the asset that was originally created by the voucher.

No Transaction

No transaction is generated for this event, and the process to remove it from PeopleSoft Asset Management must be entered manually. You can remove the created transaction from open transactions if depreciation has not been run.

If depreciation *has* been run, and the asset has been set up in the system and posted to GL, you must enter a retirement or negative addition transaction to remove it from the books.

Acquisition detail will still be inserted for the closed voucher for audit purposes, but no cost rows or financial transaction will be generated.

Retirement

Creates a retirement transaction (RET) to retire the asset that was originally created by the voucher.

If any depreciation has been taken during the interim period, it will be reversed and removed from the corporate books. Gain and loss will be calculated.

This is the default if no other option is specified.

Note: If either Negative Addition or Retirement are selected and both the first posting and the unposting of the voucher are processed in the same run of the AP/PO Interface (AMPS1000), no assets are created. The two transactions cancel each other out. The load status for both transactions is set to *Consolidated*.

See "Understanding the Asset-Loading Process (*PeopleSoft FSCM 9.2: Payables*)".

See "Understanding Asset Retirement (*PeopleSoft FSCM 9.2: Asset Management*)".

Lease Payments

Enable the options that are related to the integration between PeopleSoft Asset Management lease payments and PeopleSoft Payables. This integration enables automatic generation of vouchers for lease payments that are calculated in Asset Management, including both capital and operating leases. In addition, the lease payment schedule segregates the principal and interest of each payment and is used by the AMDPCLOS process to generate the payment accounting entries. The payments can be allocated on a monthly basis, depending upon your setup of payment schedules.

See "Understanding Leased Assets (*PeopleSoft FSCM 9.2: Asset Management*)".

Select the appropriate options for processing automatic vouchers for lease payments in the Lease Payments group box.

Note: The lease payment integration sends to PeopleSoft Payables the information that is stored in the book defined as *Lease Book* on the AM Business Unit Definition page.

Lease Interface Processing

Select to enable the lease payment interface options at the lease entry level. This integration provides the automatic generation of vouchers in PeopleSoft Payables for lease payments that are calculated in Asset Management, including both capital and operating leases. Selecting this check box also activates the other fields in the Lease Payments group box.

Note: Lease Interface Processing is deselected by default as the selection of this option makes mandatory certain fields at the lease entry level that are otherwise optional.

Auto Approve

Select to enable automatic approval. When selected, the lease payments do not require manual approval before processing to PeopleSoft Payables.

Payables BU:

Enter the Payables business unit to be used by default when creating lease schedules for integration to PeopleSoft Payables.

Warning Action**Error Out Capitalization Limit**

Select to receive warning if amount exceeds capitalization limit.

Credit Memo Notification

Set up Notification of asset-applicable credit memos from PeopleSoft Payables.

Notify To

Select one of the following options to define notification recipients:

- *None* - Select if you do not want a credit memo notification to be sent.
- *E-Mail* - Select to notify via a specific email address. Once selected, the Email field appears and you can enter the email address to which to send the notification.
- *Role* - Select to notify the user or users that are associated with a selected role. Once selected, the Roleuser field appears and you can select a specific role. The users associated with the selected role receive notification of credit memos.
- *User* - Select to notify a user ID of credit memos. Once selected, the Operator Id field appears and you can select a user ID.

Email

This field only appears if you select the *E-Mail* Notify To option. Supply an email address of the intended recipient of the credit memo notification.

Roleuser

This field only appears if you select the *Role* Notify To option. Select a specific role. Users associated with this role receive credit memo notifications.

Operator Id

This field only appears if you select the *User* Notify To option. Select a specific user ID. Those logged in with the selected user ID receive credit memo notifications.

See also "Load Assets Request Page (*PeopleSoft FSCM 9.2: Payables*)"

Billing Interface Options

Complete the appropriate definitions for processing billing transactions in the Billing Interface group box. The information entered here appears on the Create Bill tab of the Retirement page. The physical nature from PeopleSoft Asset Management is *Goods* but can be changed in Billing.

Billing Interface Processing

Select to establish processing between PeopleSoft Asset Management and PeopleSoft Billing. This activates integration between the two applications and enables the Create Bill option on the Asset Management Retirement page.

Note: PeopleSoft Billing is the only billing interface that is supported by this feature.

BI Unit

Select the Billing default business unit. The available Billing business units are established during the Billing application implementation. You can override the BI Unit as needed. Only BI Unit can be overridden on the retirement page for other PeopleSoft Billing business units whose general ledger business unit matches the PeopleSoft Asset Management business unit.

Bill Source

Select the billing source, such as *Assets*. Available options are established during the Billing application implementation. You cannot override Bill Source.

Bill Type

Select the Billing Bill Type, such as *AM*. Available options are established during the Billing application implementation. You cannot override Bill Type.

Bill By Identifier

Select the Billing Bill By Identifier such as *Assets*. Available options are established during the Billing application implementation. The Bill By Identifier will vary if the business unit is VAT enabled. You cannot override Bill By Identifier.

Note: If the Bill By Identifier should consider VAT transactions, PeopleSoft strongly recommends using the following fields: BUSINESS_UNIT_AM, BILL_SOURCE_ID, VAT_TREATMENT_GRP, COUNTRY_VAT_BILLFR, COUNTRY_VAT_BILLTO, COUNTRY_SHIP_FROM, COUNTRY_SHIP_TO, PHYSICAL_NATURE, SHIP_TO_CUST_ID, RATE_MULT, RATE_DIV, CUR_RT_SOURCE, SHIP_TO_ADDR_NUM. Otherwise: BUSINESS_UNIT_AM, BILL_SOURCE_ID, PHYSICAL_NATURE, RATE_MULT, RATE_DIV, CUR_RT_SOURCE.

See [Integrating with PeopleSoft Billing](#).

See "Understanding PeopleSoft Billing and Asset Management Integration (*PeopleSoft FSCM 9.2: Billing*)".

Space Management Allocation

Complete the appropriate definitions for processing Real Estate Management space allocation transactions in the Space Management Allocation group box. The information entered here creates the default tree

name, statistics code, and statistical account for this business unit in the Real Estate Management space allocation application.

Statistics Code Select the statistics code value associated with this space allocation.

Statistical Account Select the statistical account value associated with this space allocation.

Work Order Management

When you integrate PeopleSoft Asset Management with PeopleSoft Maintenance Management, you can define work order transfer default options.

Retire Assets Components Select this check box to enable retirement processing for components from work orders.

TRF Out Components for Reuse Select this check box to enable component transfers out for reuse from work orders.

Transfer In Components Select this check box to enable component transfers in from work orders.

Override Other Defaults Select this check box to allow default overrides from work order. This option is used for making the set up defined at BU level prevail over set up at other levels.

GIS Integration Enabled Select to enable the integration of a Geographic Information System (GIS) with PeopleSoft Maintenance Management. This check box is available for selection when GIS Integration has been enabled at the system level first (Installation Options - Overall page.)

See "Installation Options - Overall Page (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

You must also complete the required setup on the GIS Setup page (Set Up Financials/Supply Chain, Common Definitions, GIS, GIS Setup.)

See "ESRI GIS Setup Considerations (*PeopleSoft 9.2: Maintenance Management*)".

Creating PeopleSoft Asset Management Cash Generating Units

Use the Cash Generating Unit Definition (AM_CGU_DEFN) component to define cash generating units.

This topic provides an overview of cash generating units (CGUs) and describes how to create CGUs.

Page Used to Create Cash Generating Units

Page Name	Definition Name	Navigation	Usage
Cash Generating Unit Definition	AM_CGU_DEFN	Set Up Financials/Supply Chain Management, Business Unit Related, Assets, CGU Definition, Cash Generating Unit Definition	Define cash generating units to assign to individual assets.

Understanding Cash Generating Units

A cash generating unit (CGU) is the smallest identifiable group of assets that generate cash inflows from continuing use and are largely independent of the cash inflows from other assets or groups of assets. A CGU is used to assist in determining the recoverable amount of an individual asset when performing impairment assessment and processing.

After you determine how many cash generating units you require, you must define them for PeopleSoft Asset Management. You define them per business unit. Each business unit definition must already be established to associate the CGU to it.

Prerequisites to Creating Cash Generating Units

Before you can create a cash generating unit (CGU), you must select the impairment processing option when selecting installation options. This enables the Impairment Processing check boxes on the business unit pages.

See "Setting Up Application-Specific Installation Options (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

Cash Generating Unit Definition Page

Use the Cash Generating Unit Definition page (AM_CGU_DEFN) to define cash generating units to assign to individual assets.

Navigation

Set Up Financials/Supply Chain Management, Business Unit Related, Asset Management, CGU Definition, Cash Generating Unit Definition

Image: Cash Generating Unit Definition page

This example illustrates the fields and controls on the Cash Generating Unit Definition page. You can find definitions for the fields and controls later on this page.

Cash Generating Unit Definition

Business Unit IMP01
 Cash Generating Unit USCGU_01
 *Description Department - Detail Values
 Impair All Assets In This CGU

Impairment Criteria Find | View All First 1 of 1 Last
 *Field Name Department

Select Detail Values
 Select Detail Values Range of Values

Specify Values/Range of Values Personalize | Find | First 1-4 of 4 Last

*Value		
1 10000		+ -
2 10200		+ -
3 10500		+ -
4 11000		+ -

To add a new CGU, select a business unit and enter an alphanumeric CGU code. The Cash Generating Unit Definition page appears.

Description

Enter a description for this cash generating unit.

Impair All Assets In This CGU

When you select this check box, the system enables impairment processing for all assets that fall within this CGU regardless of the option to perform impairment processing at the asset level.

Impairment Criteria

Field Name

Select a field name from the list of available ChartField values.

Select Detail Values

If you select this option, you may then choose among all valid definitions for the ChartField selected. For example, if you select to define the CGU by operating unit, the valid values will be all defined operating units for this business unit.

Range of Values

If you select this option, you may then choose a range of valid definitions for the ChartField selected. For example, if you select to define the CGU by department, the valid range of

values will be all defined departments for this business unit: you will define the *from* and *to* range of departments to be included.

When you have completed your selections, save the CGU.

Related Links

"Adjusting for Asset Impairment (*PeopleSoft FSCM 9.2: Asset Management*)"

Chapter 5

Establishing Asset Processing

Establishing Asset Processing

This topic provides an overview of asset processing and discusses how to:

- Define common tables to manage assets.
 - Define asset attributes.
 - Set up asset profiles.
 - Establish asset ownership.
 - Define on-demand processing for PeopleSoft Asset Management.
 - Set up reporting options.
-

Understanding Asset Processing

When the basic accounting structure and business units that reflect the organizational and reporting structure for your enterprise have been established, you will set up the various tables and options used to manage the assets within your organization.

Asset processing covers a wide array of activities, tasks, and transactions for your enterprise. This includes:

- Identifying, classifying, and categorizing your assets.
- Recording, tracking, and maintaining physical attributes, licenses and warranties, of assets.
- Managing physical location, inventory, and custodianship of assets.
- Establishing depreciation rules and reporting for assets.
- Establishing financial, tax, and accounting treatment and reporting for assets.

PeopleSoft Asset Management is delivered with a full complement of commonly used and statutory asset management conventions. Many of these conventions likely suit the needs of your organization. If so, you can use tableset sharing to share these tables and minimize table setup tasks. Examine these tables before creating additional tables.

This topic discusses how to set up your system to enter, manage, and report on your assets.

Prerequisites

Before defining options for asset processing, you must first establish:

- Installation options and user preferences for PeopleSoft Asset Management.
- Financial common definition options such as ChartFields, accounts, departments, funds, ledgers, operating units, and so on.
- SetIDs, TableSets, and trees.
- Business units and optional cash generating units.

Related Links

"Installation Options - Asset Management Page (*PeopleSoft FSCM 9.2: Application Fundamentals*)"

"Understanding User Preferences (*PeopleSoft FSCM 9.2: Application Fundamentals*)"

"Understanding PeopleSoft ChartField Configuration (*PeopleSoft FSCM 9.2: Application Fundamentals*)"

"Setting Up Financials Audit Framework (Audit Logging) (*PeopleSoft FSCM 9.2: Application Fundamentals*)"

[Understanding Asset Management Business and Cash Generating Units](#)

Defining Common Tables to Manage Assets

This topic provides an overview of common tables and lists the pages used to define common tables.

Oracle delivers the following common tables:

- Calendars
- Currencies
- Units of Measure

Note: You can change any delivered table. To make changes to a table, however, you should make a copy of it and modify the copy. Some of these tables contain statutory information that is mandated by U.S. tax law. As well, the delivered tables are periodically upgraded when you receive new versions of PeopleSoft Asset Management. If you modify the original tables, future upgrade installations could cause problems when attempting to overwrite files that no longer exist, or overwrite files that you have modified. Use caution before changing any delivered table.

Pages Used to Define Common Tables

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Calendar Periods	DETAIL_CALENDAR1	Set Up Financials/Supply Chain, Common Definitions, Calendars/Schedules, Detail Calendar, Calendar Periods	Define the begin and end date and number of accounting periods in the fiscal year calendar. You must define calendars so that accounting entries are generated properly.
Currency Code	CURRENCY_CD_TABLE	Set Up Financials/Supply Chain, Common Definitions, Calendars/Schedules, Currency, Currency Code	Define currency common code definitions.
Units of Measure	UNITS_OF_MEASURE	Set Up Financials/Supply Chain, Common Definitions, Units of Measure	Establish general units of measure for the system.

Defining Asset Attributes

To define asset attributes, use the following components:

- To set up asset classes, use the Asset Class (ASSET_CLASS) component.
- To set up lease payment schedules, use the Payment Schedule (PYMNT_SCHED_TBL) component.
- To set up joint venture allocations, use the Joint Venture Allocation (JV_BUS_ALLOC) component.
- To set up agencies, use the Agencies (AGENCY_DEFN) component.
- To set up area definitions, use the Area Definition (AM_AREA_TBL) component.
- To set up asset types, use the Asset Type Options (AM_TYPE_OPT) component.
- To set up asset subtypes, use the Asset Subtype (AM_SUBTYPE) component.
- To set up maintenance types, use the Maintenance Types (MAINT_TYPE_DEFN) component.
- To set up location definitions, use the Location (AM_LOCATION) component.
- To set up hazardous-material codes, use the Hazardous Codes (ASSET_FSC_DEFN) component.
- To set up insurance types, use the Insurance Types (INSURANCE_TYPE) component.
- To set up units of production, use the Units of Production (UOP_DEFN) component.
- To set up user-defined asset attributes, use the Asset Attribute (AM_UD_ATTR) component.
- To set up asset property subclasses, use the Asset Property Subclass (AM_PROP_SUBTYPE) component.

- To set up asset meter types, use the Meter Types (AM_METER_TYPE) component.
- To set up asset warranties, use the Warranty Type (AM_STD_WRTY) component.
- To set up warranty templates, use the Warranty Template (AM_WRTY_TMPL) component.
- To set up equipment parts list, use the Equipment Parts List (AM_PART_LIST_TMPL) component.
- To set up criticality codes, use the Criticality Codes (AM_CRIT_LEVEL) component.

To access these components, select Set Up Financials/Supply Chain, Product Related, Asset Management.

Several procedures and options are available for establishing the core tables for PeopleSoft Asset Management. As previously noted, many of these tables are optional or conditional. Some are required before you can enter assets into the system; these tables are noted as such.

This topic discusses how to:

- Set up asset classes.
- Define lease payment schedules.
- Define FERC codes.
- Define joint venture allocations.
- Define maintenance types.
- Set up units of production.
- Maintain indexes and units of production tables.
- Define agencies.
- Set up area definitions.
- Define asset type options.
- Define asset subtypes.
- Define asset attributes.
- Define property subclasses.
- Set up hazardous codes.
- Set up location codes.
- Set up insurance types.
- Set up asset physical definitions.
- Set up asset meter types.
- Set up asset warranties.
- Set up equipment parts lists.

- Set up criticality codes.

Note: You can also set up attribute groups.

See "PeopleSoft Maintenance Management Integration with PeopleSoft Asset Management (*PeopleSoft 9.2: Maintenance Management*)".

Pages Used to Define Asset Attributes

Page Name	Definition Name	Navigation	Usage
Asset Class	ASSET_CLASS_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Asset Classes	Maintain asset classes. Asset classes are set up at the tableset level.
VAT Defaults Setup (value-added tax defaults setup)	VAT_DEFAULTS_DTL	Click the VAT Default link on the Asset Class definition page.	Specify VAT defaults setup.
Payment Schedules	LEASE_SCH_ID	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Payment Schedules, Payment Schedules	Add or modify payment schedules. When adding leased assets to your system, you must have at least one payment schedule defined.
FERC Code	FERC_CD_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, FERC Code, FERC Code	Establish FERC (Federal Energy Regulatory Commission) codes for asset categories that are used in regulatory reporting.
Joint Venture Allocation	JV_BUS_ALLOC	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Joint Venture Allocation, Joint Venture Allocation	Define the percentage of asset ownership to allocate to each joint venture participant. Use this page to set up the Joint Venture Allocation table.
Maintenance Types	MAINT_TYPE_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Service and Repair, Maintenance Types, Maintenance Types	Define maintenance types.
Units of Production	UOP_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Units of Production	Set up units of production definitions.
Load UOP and Index Tables	RUN_AMIF2000	Asset Management, Send/Receive Information, Load Interface, Receive UOP and Index Tables	Load units of production and index tables.

Page Name	Definition Name	Navigation	Usage
Agencies	AGENCY_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Physical Definitions, Agencies, Agencies	Create agency codes. Keep track of the registration and licenses of an asset by using the information that is set up in Agency tables.
Area Definition	AM_AREA_TBL	Set Up Financials/Supply Chain, Product Related, Asset Management, Physical Definitions, Area Definition, Area Definition	Define an asset area within a location.
Asset Type Options	AM_TYPE_OPT	Set Up Financials/Supply Chain, Product Related, Asset Management, Physical Definitions, Asset Type Options, Asset Type Options	Define physical asset types to be applied to individual assets. Oracle delivers ten asset types: <i>Hardware, Software, Equipment, Property, Fleet, Machinery, Furniture, Facility, Intangible, Other</i> .
Define Asset Subtype	AM_SUBTYPE	Set Up Financials/Supply Chain, Product Related, Asset Management, Physical Definitions, Asset Subtype, Define Asset Subtype	Define asset subtypes as they relate to asset types. For example, if the asset type is <i>Hardware</i> , an asset subtype may be defined for a <i>Laptop</i> .
Define Asset Attribute	AM_UD_ATTR	Set Up Financials/Supply Chain, Product Related, Asset Management, Physical Definitions, Define Asset Attribute, Define Asset Attribute	Define any asset physical attribute to be associated with an asset.
Define Property Subclass	AM_PROP_SUBCLASS	Set Up Financials/Supply Chain, Product Related, Asset Management, Physical Definitions, Asset Property Subclass, Define Property Subclass	Define property asset subclasses as they relate to asset property classes: <i>Site, Building, Floor, Area, Space</i> .
Hazardous Codes	ASSET_FSC_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Physical Definitions, Hazardous Codes, Hazardous Codes	Define hazardous-asset codes. The PeopleSoft system is delivered with the Federal Supply Class (FSC) codes, which are U.S. federal codes that identify predominant and significant hazardous materials. You may add other classifications.
Location Definition	AM_LOCATION_TBL	Set Up Financials/Supply Chain, Product Related, Asset Management, Physical Definitions, Location Definition, Location Definition	Set up locations.

Page Name	Definition Name	Navigation	Usage
Detail	MAINT_CONTRACT_01	Asset Management, Service and Maintenance, Maintenance Contract Terms, Detail	Define the detail terms for maintenance contracts by entering the effective, expiration, and contract dates, and the contract cost and supplier information.
Coverage	MAINT_CONTRACT_02	Asset Management, Service and Maintenance, Maintenance Contract Terms, Coverage	Define the maintenance contract coverage, including contact information.
Insurance Types	INSURANCE_TYPE	Set Up Financials/Supply Chain, Product Related, Asset Management, Service and Repair, Insurance Types, Insurance Types	Enter different types of insurance, such as liability for automobiles or property.
Transaction Information	UOP_DEFN_WRK	Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Units of Production, Transaction Information	Generate open transactions. Each time new detail is added to this table, you can generate open transactions for each asset associated with it.
Work Order Options for Components	AM_WOM_OPT_SUBTYPE	Click the Work Order Options for Components link on the Define Asset Subtype page.	Define Work Management work order options.
Meter Type Definition	AM_METER_TYPE1	Set Up Financials/Supply Chain, Product Related, Asset Management, Service and Repair, Meter Types, Meter Type Definition	Define meter types.
Meter Type Comments	AM_METER_TYPE2	Set Up Financials/Supply Chain, Product Related, Asset Management, Service and Repair, Meter Types, Meter Type Comments	Add comments that are relevant to meter type definition.
Standard Warranties	AM_STD_WRTY	Set Up Financials/Supply Chain, Product Related, Asset Management, Service and Repair, Standard Warranties	Define standard warranties.
Warranty Templates	AM_WRTY_TMPL	Set Up Financials/Supply Chain, Product Related, Asset Management, Service and Repair, Warranty Templates	Set up templates for warranty types to apply to asset types.

Page Name	Definition Name	Navigation	Usage
Equipment Parts List	AM_PART_LIST_TMPL	Set Up Financials/Supply Chain, Product Related, Asset Management, Service and Repair, Equipment Parts List	Define equipment parts lists to be associated with asset classes, groups, categories, types and subtypes, or other asset definitions.
Criticality Codes	AM_CRIT_LEVEL	Set Up Financials/Supply Chain, Product Related, Asset Management, Service and Repair, Criticality Codes, Criticality Codes	Establish levels of criticality.

Asset Classes Page

Use the Asset Class page (ASSET_CLASS_DEFN) to maintain asset classes.

Asset classes are set up at the tableset level.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Asset Classes

Image: Asset Classes page

This example illustrates the fields and controls on the Asset Classes page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Asset Classes' page with the following details:

- Page Title:** Asset Classes
- SetID:** SHARE
- Asset Class:** BUILDING
- Asset Class Detail:** Find | View All | First 1 of 1 Last
- *Effective Date:** 01/01/1900
- *Status:** Active
- Description:** BUILDING
- Years of VAT Recoverability:** (empty field)
- VAT Default:** (empty field)
- Comment:** (empty text area)

To add a new asset class, select the SetID and enter the name of the asset class. Complete the fields on the Asset Classes page as appropriate.

Use asset class to classify assets for reporting purposes. It can be used in combination with the category code to refine asset classification. For example, an executive desk is categorized as furniture and fixtures for the balance sheet. Within the broad category of furniture and fixtures, you can use an asset class code to specifically identify the asset as a desk.

For defining asset classes, Oracle provides the option to define value-added tax (VAT) processing defaults as well.

Defining Asset Class as VAT Driver

Asset class is also used as a VAT driver. Create classifications of assets based on the VAT treatment. For example, treatment of assets such as automobiles may be different from that of assets such as buildings or leases. In this way, the asset class can be used to determine the VAT treatment.

VAT defaults are also set up at the business unit level.

See [VAT Defaults Setup Page](#).

Years of VAT Recoverability

Enter the number of years of VAT recoverability adjustment for the asset class. The number of years can be different from the useful life of the asset and is dictated by VAT legislation. For example, the number of years for recoverability for buildings is 20 and for all other asset classes is 5 years.

Payment Schedules page

Use the Payment Schedules page (LEASE_SCH_ID) to add or modify payment schedules.

When adding leased assets to your system, you must have at least one payment schedule defined.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Payment Schedules, Payment Schedules

Image: Payment Schedule page

This example illustrates the fields and controls on the Payment Schedule page. You can find definitions for the fields and controls later on this page.

Payment Schedules

SetID: SHARE Payment Schedule ID: AA General Payment Schedule

Payment Schedule

Number of Payments Per Year: 12 Prorate Lease Expense

Description: This payment schedule will be setup for monthly lease calculations.

Generate Schedule Parameters

Begin Date: 01/01/2009 Lease Term (Periods):
 End Date: 12/31/2009 Payment Frequency: Monthly
 End Of Month Due Date Populate

Payment Dates Personalize | Find | First 1-12 of 12 Last

Payment Date		
01/01/2009	+	-
02/01/2009	+	-
03/01/2009	+	-
04/01/2009	+	-
05/01/2009	+	-
06/01/2009	+	-
07/01/2009	+	-
08/01/2009	+	-
09/01/2009	+	-
10/01/2009	+	-
11/01/2009	+	-
12/01/2009	+	-

When working with leased assets, you must define payment schedules to be assigned to the leased assets.

You must have at least one payment schedule defined when working with leased assets. PeopleSoft Asset Management delivers four payment schedules in the SHARE tableset.

Prorate Lease Expense

Select to prorate the accounting entries that are generated for lease payments by the depreciation close process on a monthly basis in accordance with Generally Accepted Accounting Principles (GAAP). The payment schedule segregates the

interest and principal for proper classification of accounting entries.

End Of Month Due Date

Select to always schedule the payment on the last day of the month, no matter what date is entered in the Begin Date field.

Populate

Click to enable PeopleSoft Asset Management to automatically enter the payment dates for the time period that you defined. Be sure to enter the number of payments per year to ensure that PeopleSoft Asset Management can determine the number of lease payments for the lease schedule.

See "Understanding Leased Assets (*PeopleSoft FSCM 9.2: Asset Management*)".

FERC Code Page

Use the FERC Code page (FERC_CD_DEFN) to establish FERC (Federal Energy Regulatory Commission) codes for asset categories that are used in regulatory reporting.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, FERC Code, FERC Code

Image: FERC Code page

This example illustrates the fields and controls on the FERC Code page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'FERC Code' page in a web browser. At the top, the page title is 'FERC Code'. Below the title, there are two lines of text: 'SetID SHARE' and 'FERC Code 102'. The main content area is a form with a light blue header bar that says 'FERC Code'. Inside the form, there are several fields: '*Effective Date' with a date picker set to '01/01/1900', '*Status' with a dropdown menu set to 'Active', 'Description' with a text box containing 'Plant Purchased or Sold', and 'Short Description' with a text box containing 'Plant'. At the bottom of the form, there is a 'Comment' label followed by a large empty text area for entering notes.

Add or update FERC codes in accordance with the U.S. Federal Energy Regulatory Commission. FERC codes are used to associate assets with the FERC Uniform System of Accounts for utilities. They are used for regulatory reporting and do not affect any calculations.

Joint Venture Allocation Page

Use the Joint Venture Allocation page (JV_BUS_ALLOC) to define the percentage of asset ownership to allocate to each joint venture participant.

Use this page to set up the Joint Venture Allocation table.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Joint Venture Allocation, Joint Venture Allocation

Enter each participating business unit and its allocated percentage of equity in the shared assets. The sum of these percentages must equal 100 percent.

The joint venture allocation table affects only newly added assets. Changes made to the allocation table will not affect existing assets. To change ownership percentages of existing assets, you must run a mass change using the template that is supplied for this purpose. These joint venture mass change templates enable you to:

1. Add a joint venture business unit.
2. Remove a joint venture business unit.
3. Change joint venture ownership allocations.

When you have changed the assets, change the allocation table to reflect the new equity percentages.

Note: The joint venture allocation as defined in the allocation table need not match the actual ownership percentages. For example, if two companies enter a joint venture on a 60/40 basis, one of them can sell the joint venture asset on a 70/30 basis—effectively giving one party a discount while the other pays a premium. In this case, you would first enter the asset at the joint venture business unit level, then change the cost apportionment by using mass change.

Related Links

"Understanding Joint Venture Processing (*PeopleSoft FSCM 9.2: Asset Management*)"

Maintenance Types Page

Use the Maintenance Types page (MAINT_TYPE_DEFN) to define maintenance types.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Service and Repair, Maintenance Types, Maintenance Types

Image: Maintenance Types page

This example illustrates the fields and controls on the Maintenance Types page. You can find definitions for the fields and controls later on this page.

Maintenance types identify the type of maintenance and maintenance procedures to follow for a particular asset. For example, you might establish a *Tune Up* maintenance code that specifies routine maintenance for an automobile.

See "Understanding Asset Maintenance, Repair, Warranties, and Insurance (*PeopleSoft FSCM 9.2: Asset Management*)".

Units of Production Page

Use the Units of Production page (UOP_DEFN) to set up units of production definitions.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Units of Production

When you depreciate assets by using the units of production method, you must set up units of production definitions. This table defines the maximum units that an asset can produce and how many units have been posted for each period.

Adding and Adjusting Units of Production Detail Page

Access the Transaction Information page.

Transaction Date	Reflects the date on which you made the changes.
Accounting Date	Reflects the date on which the entered changes will affect your general ledger.

Both dates are used in recalculating depreciation. The difference between the transaction date and the accounting date determines whether production detail for this transaction will be posted as accumulated production.

The difference between the transaction date and the accounting date determines whether any prior period production needs to be posted. For example, consider a machine that was acquired and placed in service on March 15, 2008 but did not get entered in PeopleSoft Asset Management until August 1, 2008. All general ledger periods prior to August are closed. In this case, PeopleSoft Asset Management automatically posts any accumulated production to the general ledger in August.

Unlike accumulated depreciation, accumulated production is posted exactly the same as any other production detail. Nothing distinguishes it as accumulated production.

Accumulated production for a new units of production ID should be posted on a date that is before any assets associated with the units of production ID are added.

Related Links

"Understanding Asset Information Flow (*PeopleSoft FSCM 9.2: Asset Management*)"

"Understanding Depreciation Processing (*PeopleSoft FSCM 9.2: Asset Management*)"

Maintaining Indexes and Units of Production Tables

You will periodically update the information in your Index and Units of Production tables when you receive new information. You can load or update the Index and Units of Production tables automatically using the AMIF2000. This process takes data in a fixed length format ASCII file and loads it into the appropriate table.

Files to be loaded into the Index table should be in this format:

Field	Length
SETID	5
INDEX_NAME	20
EFFDT	8 (MM/DD/YY)
DESCR	30
INDEX_DETAIL_NAME	35
INDEX_AMOUNT	15

Files to be loaded into the Units of Production table should be in this format:

Field	Length
SETID	5
UOP_ID	10
DESCR	30
UOP_IN_SERVICE_DT	8 (MM/DD/YY)
UOP_MAX_UNITS	12
UNIT_OF_MEASURE	3
UOP_POSTING_DT	8 (MM/DD/YY)
UOP_UNITS	12

Defining Asset Physical Definitions

To define asset physical definitions, use the following components:

- Agencies (AGENCY_DEFN)
- Area Definition (AM_AREA_TBL)
- Asset Type Options (AM_TYPE_OPT).
- Asset Subtype (AM_SUBTYPE).
- Asset Attribute (AM_UD_ATTR).
- Asset Property Subclass (AM_PROP_SUBTYPE).
- Hazardous Codes (ASSET_FSC_DEFN)
- Asset Meter Types (AM_METER_TYPE)
- Location Definition (AM_LOCATION)

To access these components, select Set Up Financials/Supply Chain, Product Related, Asset Management, Physical Definitions.

Agencies Page

Use the Agencies page (AGENCY_DEFN) to create agency codes.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Physical Definitions, Agencies, Agencies

Image: Agencies Page

This example illustrates the fields and controls on the Agencies Page. You can find definitions for the fields and controls later on this page.

The screenshot shows a web interface for managing agencies. At the top, there are tabs for 'SetID SHARE' and 'Agency ID DMV'. Below this is a header for 'Agency Information' with navigation options: 'Find | View All', 'First', '1 of 1', and 'Last'. The form contains several fields:

- *Effective Date: 01/01/1900
- *Status: Active (dropdown menu)
- Agency Name: Department of Motor Vehicles

 Below the Agency Information section is the 'Contact Information' section, which includes:

- Name: Eric Harvie
- Addr: 100 Main Street
- Phone: 800/999-9999
- Fax: (empty field)

 At the bottom, there is a 'Comments' section with a large text area and a small icon in the bottom right corner.

Keep track of the registration and licenses of an asset by using the information that is set up in Agency tables. Only agency IDs that are set up here can be entered on the Asset License/Registration page.

Area Definition Page

Use the Area Definition page (AM_AREA_TBL) to define an asset area within a location.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Physical Definitions, Area Definition, Area Definition

Image: Area Definition Page

This example illustrates the fields and controls on the Area Definition Page. You can find definitions for the fields and controls later on this page.

The screenshot displays the 'Area Definition' page. At the top, the title 'Area Definition' is shown. Below it, the following information is displayed:

- SetID: SHARE
- Location: US001 USA - New York
- Area ID: PARKING A

The 'Area Information' section contains the following fields and controls:

- *Effective Date: 01/01/1900 (with a calendar icon)
- *Status: Active (with a dropdown arrow)
- *Description: Parking A - HQ
- Area Detail: Parking lot A is located on North Street, underground level. (with a text area icon)

Navigation controls at the top right of the 'Area Information' section include 'Find | View All', 'First', '1 of 1', and 'Last'.

The Area Definition enables you to create a more granular level that further identifies the asset within a location. In PeopleSoft Asset Management, an asset can be physically located by region, location, and area.

Note: The system clears the area ID for an asset when you move that asset to a new location. You can then reassign new area IDs to the asset, as appropriate.

Asset Type Options Page

Use the Asset Type Options page (AM_TYPE_OPT) to define physical asset types to be applied to individual assets.

Oracle delivers ten asset types: Hardware, Software, Equipment, Property, Fleet, Machinery, Furniture, Facility, Intangible, Other.

You can assign the appropriate options that apply to each asset type for PeopleSoft Maintenance Management work orders and InterUnit Transfer Default values.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Physical Definitions, Asset Type Options, Asset Type Options

Image: Asset Type Options Page

This example illustrates the fields and controls on the Asset Type Options Page. You can find definitions for the fields and controls later on this page.

Retire Assets Components

Select to enable retirement processing for components from work orders.

TRF Out Components for Reuse

Select to enable component transfers out for reuse from work orders.

Transfer In Components

Select to enable component transfers in from work orders.

Asset Attribute Groups Info

Select to enable attribute group transfers in from work orders.

Asset Acquisition Info

Select to include information derived from the Asset Acquisition Detail (ASSET_ACQ_DETAIL) page and links (ASSET_ACQ_DET_AP, ASSET_ACQ_DET_VAT).

Asset Attributes Info

Select to include information derived from the Asset Location/Comments/Attributes (ASSET_IMAGE) page.

Asset License/Register Info

Select to include information derived from the Asset Custodian/License/Manufacturer (ASSET_CUSTODIAN) page and links (ASSET_LIC_ADDR_SEC).

Asset Lease Info

Select to include information derived from the Leased Assets component pages (ASSET_LEASE_01, ASSET_LEASE_02, ASSET_LEASE_05, ASSET_LEASE_03).

Asset Non-Capitalized Cost

Select to include information derived from the Asset Acquisition Detail (ASSET_ACQ_DETAIL) page and links (ASSET_ACQ_DET_AP, ASSET_ACQ_DET_VAT).

Asset Maintenance Info	Select to include information derived from the Track Service and Repairs component and Meter Reading component pages (ASSET_MAINT_01, ASSET_MAINT_01_S, AM_METER_READ).
Asset Comments	Select to include information derived from the Asset Location/Comments/Attributes (ASSET_IMAGE) page.
Asset Warranty Info	Select to include information derived from the Asset Custodian/License/Manufacturer page (ASSET_CUSTODIAN) and links (ASSET_WARRANTY).
Asset Insurance Info	Select to include information derived from the Asset Custodian/License/Manufacturer page (ASSET_CUSTODIAN) and links (ASSET_INSURANCE).
Asset Inspection Info	Select to include information derived from the Asset Custodian/License/Manufacturer page (ASSET_CUSTODIAN) and links (ASSET_INSPECTION).

Define Asset Subtype Page

Use the Define Asset Subtype page (AM_SUBTYPE) to define asset subtypes as they relate to asset types.

For example, if the asset type is Hardware, an asset subtype may be defined for a Laptop.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Physical Definitions, Asset Subtype, Define Asset Subtype

Image: Define Asset Subtype Page

This example illustrates the fields and controls on the Define Asset Subtype Page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Define Asset Subtype' page with the following fields and controls:

- SetID:** SHARE
- Asset Type:** IT Hardware
- Asset Subtype:** DESKTOP
- *Description:** Desktop
- Short Description:** Desktop
- IT Subtype:** DESKTOP
- Work Order Options for Components:**
 - Effective Date:** 01/01/1900
 - Status:** Active
 - Use As Tool:**
 - Linear Asset:**
 - Cost Rate:** 1.00
 - Currency Code:** USD
 - Billing Rate:** (empty)
 - Unit of Measure:** EA

IT Subtype

Map the Asset Subtype to an IT Subtype to create the association between the two fields for tracking IT assets within the asset repository for PeopleSoft IT Asset Management.

Note: The IT Subtype field appears only when PeopleSoft IT Asset Management is installed.

See "Assets, Asset Types, and Asset Subtypes (*PeopleSoft FSCM 9.2: IT Asset Management*)".

See "IT Subtypes (*PeopleSoft FSCM 9.2: IT Asset Management*)".

Use As Tool

Check whether this subtype is used as a tool in support of another asset.

When the asset specifies an asset subtype, the system applies the Use As Tool field value from the asset definition level.

When defining an asset, you can associate it with a profile, such as *Building* or *Automobile*. If no profile is specified for the asset, the asset subtype value Use As Tool will apply when this subtype is selected for the asset. The following describes the system validation process: When working with assets in *Add* mode only, if no asset subtype is specified for the asset, the system checks the profile. From the profile definition, the system will populate the new asset with the asset type and asset subtype values. When the profile specifies an asset subtype, the system sets the Use As Tool field value to the same value of the asset subtype as defined in the associated profile. When the profile does not specify an asset subtype, no values are provided by default because the Use As Tool field value is blank on the profile and the newly added asset will follow suit.

Linear Asset

Identify this asset subtype as one that has coordinates for its start and end points, for example, a train track, a pipeline, or a roadway. You can override this option from the basic component when adding or updating assets.

Cost Rate and Currency Code

Enter the cost rate and currency to be used if a cost is applied for this asset subtype.

Billing Rate

Enter the billing rate to be used if the use of the asset subtype is to be billed.

Unit of Measure

Enter the units measured for cost and billing.

Define Asset Attribute Page

Use the Define Asset Attribute page (AM_UD_ATTR) to define any asset physical attribute to be associated with an asset.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Physical Definitions, Define Asset Attribute, Define Asset Attribute

Image: Define Asset Attribute Page

This example illustrates the fields and controls on the Define Asset Attribute Page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Define Asset Attribute' page. At the top, the attribute is identified as 'Attribute CRITICAL'. Below this is a table with the following fields:

Information		Find View All	First	1 of 1	Last
*Effective Date	<input type="text" value="01/01/2011"/>		<input type="button" value="+"/>	<input type="button" value="-"/>	
*Status	<input type="text" value="Active"/>				
Attribute Name	<input type="text" value="CRITICAL"/>				
*Description	<input type="text" value="Critical Component Production"/>				

Enter user-defined asset attributes to assign to assets. For example, you can create asset attributes to specify a quality, aspect, version, or other characteristic that can be applied to an asset. Asset attributes are optional.

Note: Asset attributes should not be confused with attribute groups. Asset attributes are used widely within PeopleSoft Asset Management to characterize assets regardless of the type of asset. Attribute groups are logical records that store the specific attributes that are of a particular interest for a certain type of asset. The attributes that are part of the attribute group are defined on the Fields Summary page within PeopleSoft Maintenance Management, Supplemental Data (Set Up Financials/Supply Chain, Product Related, Maintenance Management, Supplemental Data, Define Record.)

Define Property Subclass Page

Use the Define Property Subclass page (AM_PROP_SUBCLASS) to define property asset subclasses as they relate to asset property classes: Site, Building, Floor, Area, Space.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Physical Definitions, Asset Property Subclass, Define Property Subclass

Image: Define Property Subclass Page

This example illustrates the fields and controls on the Define Property Subclass Page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Define Property Subclass' page. At the top, it displays 'SetID SHARE', 'Property Subclass Code WA', and 'Property Class Site'. Below this is a search bar with 'Find | View All' and navigation controls for 'First', '1 of 1', and 'Last'. The main form area contains several fields: '*Effective Date' with a date picker set to '01/01/1900', '*Status' with a dropdown menu set to 'Inactive', '*Instance Name' with the text 'Waiting Area', and '*Description' with the text 'Waiting Area'. There are also '+' and '-' buttons next to the status dropdown.

Define property subclass codes to apply to property asset classes: *Site, Building, Floor, Area, Space*. For example, you can define the corporate sites and further enter property subclasses for the buildings located on the site.

Hazardous Codes Page

Use the Hazardous Codes page (ASSET_FSC_DEFN) to define hazardous-asset codes.

The PeopleSoft system is delivered with the Federal Supply Class (FSC) codes, which are U.S. federal codes that identify predominant and significant hazardous materials. You may add other classifications.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Physical Definitions, Hazardous Codes, Hazardous Codes

When you manage assets that can be classified as hazardous material, you must maintain the Hazardous Material codes table. U.S. Federal Supply Class codes are delivered with PeopleSoft Asset Management, and you can add codes to supplement the list. Hazardous assets can be reported using asset search functions, and storage locations can be managed with specific building, room, floor, and longitudinal and latitudinal information added to the location page that is associated with the asset.

Note: Hazardous material and waste is solid, liquid, or gaseous waste, or a combination of these wastes, that because of its quantity or concentration, or its physical, chemical, or infectious characteristics, may cause a significant increase in mortality or an increase in serious irreversible or incapacitating illness, or pose a substantial present or potential hazard to human health or the environment when improperly treated, stored, transported, disposed of, or otherwise managed (according to the United States Environmental Protection Agency).

Meter Type Definition Page

Use the Meter Type Definition page (AM_METER_TYPE1) to define meter types.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Service and Repair, Meter Types, Meter Type Definition

Image: Meter Type Definition page

This example illustrates the fields and controls on the Meter Type Definition page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Meter Type Definition' page. At the top, there are tabs for 'Meter Type Definition' and 'Meter Type Comments'. Below the tabs, the 'SetID' is 'SHARE' and the 'Meter Type' is 'ODOMETER'. The 'Status' is set to 'Active'. The 'Description' field contains 'ODOMETER'. The '*UOM' is 'MIL' with the unit 'Miles'. The 'Lower Limit' is '0.0000' and the 'Upper Limit' is '999999.0000'. The 'No. of Readings' is '5'. There are checkboxes for 'Required for Work Order' (unchecked) and 'Maintain Daily Average' (checked). Under 'Meter Options', 'Increasing' is selected with a radio button, and 'Allow Rollover' is checked. There are also radio buttons for 'Decreasing' and 'Tolerance Range'. At the bottom, there are input fields for 'Lower Tolerance' (0.0000) and 'Upper Tolerance'.

When you manage assets that use meters to track asset usage or that provide some other type of measurement associated with the asset, you need to define meter types.

Define meter types within SetIDs.

Status

Set the meter status. Values are:

Active: The meter is actively measuring.

Inactive: The meter is not actively measuring but is available.

Description

Description

(Required) Enter a meter description.

UOM (units of measure)

(Required) Enter the units by which the meter will measure, such as miles, kilometers, gallons, liters, square feet, and so on.

Note: Many units of measure are provided with PeopleSoft software. You must define units of measure if the measurement is not common and not delivered with PeopleSoft software.

See "Units of Measure Page (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

Lower Limit and Upper Limit

(Required) Enter the lowest and highest value that the meter can read. The lower limit is never greater or equal to the upper limit. The upper limit is never less than or equal to the lower limit.

Required for Work Order

Select to require this meter type in a work order before the status of the work order can be set to complete. This option is available only when PeopleSoft Maintenance Management is installed.

Maintain Daily Average

Select to maintain a daily average. The average is informational only for preventive maintenance schedules in PeopleSoft Maintenance Management. The option is not selected by default.

No. of Readings (number of readings) Enter the number of readings to calculate the daily average. This is required when Maintain Daily Average is selected.

Meter Options**Increasing or Decreasing**

Select Increasing if the meter should increment along the useful life of the asset by the units of measure selected. Select Decreasing if the meter should decrement along the useful life of the asset by the unit of measure selected. The Increasing option is selected by default.

Allow Rollover

Select if the meter should reset to zero after reaching its defined maximum. It is selected by default.

Tolerance Range

Select to establish a tolerance range for a maintenance event. When this option is selected, the tolerance range fields become active.

Lower Tolerance and Upper Tolerance

Enter the tolerance range. For example, a piece of construction hydraulic equipment may use a pressure meter. If the meter falls below the lower tolerance or above the upper tolerance, you might initiate maintenance or replacement as needed.

See "Understanding Preventive Maintenance Work Orders (*PeopleSoft 9.2: Maintenance Management*)".

Setting Up Asset Warranties

This section provides an overview of warranties and discusses how to:

- Set up standard warranties.
- Set up warranty templates.

Understanding Warranties

For the system to automatically assign one or more warranties to each newly acquired asset, standard equipment warranties and equipment warranty defaults must be defined. Each asset that is added to the repository is available to have the appropriate warranties automatically attached to it. You can update a

warranty for an asset at any time after the addition of the asset to the asset repository, including changing the terms of the warranty, renewing or voiding the warranty associated with the asset, or making other notable changes in coverages or terms.

A warranty is established as a standard warranty that is applied to a single asset. Or a generic warranty that can be applied to multiple assets can be defined as a warranty template. This is useful when the same terms of a general warranty apply to many assets, such as multiple computer workstations or truck tires for a fleet of trucks. It is also useful when you are applying multiple standard warranties to assets. For example, an asset may be delivered with a manufacturer's warranty and an additional extended warranty that is purchased separately and provides different coverages.

Related Links

"Understanding Asset Maintenance, Repair, Warranties, and Insurance (*PeopleSoft FSCM 9.2: Asset Management*)"

Standard Warranties Page

Use the Standard Warranties page (AM_STD_WRTY) to define standard warranties.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Service and Repair, Standard Warranties

Image: Standard Warranties Page

This example illustrates the fields and controls on the Standard Warranties Page. You can find definitions for the fields and controls later on this page.

Enter the standard warranty information for an asset type, category, class, or other asset definition. Use the standard warranty to associate it with specific asset IDs.

Manufacturer's Warranty

Select if the warranty is the original manufacturer's warranty.

Coverage

Enter a description of the warranty.

Days for Refund

Enter the number of days during which the asset is eligible for refund.

Days to Return

Enter the number of days during which the asset is eligible to be returned.

Days for Replacement

Enter the number of days during which the asset is eligible for replacement.

- RMA Required** Select if an RMA (Return Material Authorization) is to be accompanied with the asset before it can be returned under warranty.
- Loaner Provided** Select if the asset will be replaced with a similar loaned asset while under repair.
- On-Site Repair** Select if the asset is eligible for repair at your place of business.
- Warranty Transferable** Select if this warranty transfers when ownership of the asset transfers.
- Warranty Life** Select the meters that can be associated with the asset to measure warranty life. For example, a vehicle usually has a warranted life based on miles which are measured by the vehicle odometer.
- Entitlement** Enter a summary of what the warranty specifically entitles the owner to receive.

Warranty Templates Page


Use the Warranty Templates page (AM_WRTY_TMPL) to set up templates for warranty types to apply to asset types.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Service and Repair, Warranty Templates

Image: Warranty Templates Page

This example illustrates the fields and controls on the Warranty Templates Page. You can find definitions for the fields and controls later on this page.



Define warranty templates that can be applied to multiple assets at one time, such as assets defined by asset type, category, class or other asset definition.

Select all standard warranties that apply to the individual asset category, class, type, and so on.

Equipment Parts List Page

Use the Equipment Parts List page (AM_PART_LIST_TMPL) to define equipment parts lists to be associated with asset classes, groups, categories, types and subtypes, or other asset definitions.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Service and Repair, Equipment Parts List

Image: Equipment Parts List page

This example illustrates the fields and controls on the Equipment Parts List page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Equipment Parts List' page with the following search criteria:

- SetID: SHARE
- *Status: Active
- *Asset Type: Facility
- Manufacturer ID: BELLANDGOSSET
- Parts List Template: B&GWATERPUMP
- Asset Subtype: HVAC/HEATING
- Model: (empty)
- Product Version: (empty)

Below the search criteria is a 'Parts Details' section with a table of parts. The table has columns for Seq, Item ID, Item Description, *Quantity, *Unit of Measure, and Asset. There are 6 rows of data.

Seq	Item ID	Item Description	*Quantity	*Unit of Measure	Asset
1	30020	Volute Gasket	1.0000	EA	<input type="checkbox"/>
2	30010	Single Row Radial Ball Bearing	2.0000	EA	<input type="checkbox"/>
3	30050	Seal Kit	1.0000	EA	<input type="checkbox"/>
4	30051	Sleeve Kit	1.0000	EA	<input type="checkbox"/>
5	60020	Bearing Bracket	1.0000	EA	<input type="checkbox"/>
6	60021	Pump Impeller	1.0000	EA	<input type="checkbox"/>

Asset equipment parts lists (EPL) are maintained by SetID. You can establish a parts list to correspond to asset classes, groups, categories, types, and subtypes, or to any asset definition. The EPL can then be associated with a specific asset ID.

Related Links

"Adding and Maintaining Asset Information (*PeopleSoft FSCM 9.2: Asset Management*)"

Criticality Codes Page





Use the Criticality Codes page (AM_CRIT_LEVEL) to establish levels of criticality.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Service and Repair, Criticality Codes, Criticality Codes

Image: Criticality Codes page

This example illustrates the fields and controls on the Criticality Codes page. You can find definitions for the fields and controls later on this page.

Criticality Codes					
Criticality Detail		Personalize Find  		First  1-3 of 3  Last	
	*Asset Criticality	*Description	*Factor		
1	<input type="text" value="01"/>	<input type="text" value="High"/>	<input type="text" value="1"/>	<input type="button" value="+"/>	<input type="button" value="-"/>
2	<input type="text" value="02"/>	<input type="text" value="Medium"/>	<input type="text" value="2"/>	<input type="button" value="+"/>	<input type="button" value="-"/>
3	<input type="text" value="03"/>	<input type="text" value="Low"/>	<input type="text" value="3"/>	<input type="button" value="+"/>	<input type="button" value="-"/>

Asset Criticality

Enter a code that identifies the importance of this asset.

Description

Enter a description of the asset criticality code. For example, A1 is important, A2 is moderate, and A3 is low.

Factor

Enter a weighting factor that the system uses for sorting and prioritizing the criticality codes.

Setting Up Asset Profiles

Use the Asset Profile Definition (PROFILE) component to define asset profiles.

This topic provides an overview of asset profiles and discusses how to:

- Define asset profiles.
- Specify asset books for a profile.
 - Set up special terms for depreciation methods information.
 - Set up inflation information for a profile.
 - Set up salvage rounding rules.
- Specify tax attributes in a profile.
- Specify child asset inheritance attributes in a profile.

Pages Used to Set Up Asset Profiles

Page Name	Definition Name	Navigation	Usage
Asset Profile	PROFILE_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Profiles, Asset Profiles	Define asset profiles.
Asset Profile - Depreciation	PROFILE_BK_01	Set Up Financials/Supply Chain, Product Related, Asset Management, Profiles, Asset Profiles, Depreciation	Identify the criteria to use in depreciation calculations.
Depreciation Method Information	PROFILE_DEPR_DETL	Select the Special Depr check box and click Special Terms on the Depreciation page of the Asset Profile component.	Set special depreciation terms for an asset profile and select an accounting method for these special terms. These are commonly used to meet depreciation requirements for specific countries.
Inflation Information	PROFILE_SEC	Set Up Financials/Supply Chain, Product Related, Asset Management, Profiles, Asset Profiles, Depreciation, Inflation Information	Establish an inflation adjustment factor by selecting the market index and rate to apply.
Salvage Rounding Options	SALVAGE_OPTION_SEC	Click Salvage Rounding Options on the Asset Profile - Depreciation page.	Enter options for rounding depreciation amounts for this book. This is for use in Japan.
Asset Profile - Tax	PROFILE_BK_03	Set Up Financials/Supply Chain, Product Related, Asset Management, Profiles, Asset Profiles, Tax	Specify property type and tax depreciation criteria and identify which tax credits will be used by the profile.
Asset Profile - Child Asset Inheritance	PROFILE_PAR_BK_ECD	Set Up Financials/Supply Chain, Product Related, Asset Management, Profiles, Asset Profiles, Child Asset Inheritance	Specify child asset attributes that will be used by the profile and inherited from the parent asset for Express Add, Basic Add, and batch-created assets. The inheritance based on the selected items happens upon defaulting the profile in Express Add and capitalizing the asset in Basic Add, and when you are using Default Profile processing in the Transaction Loader if the Business Unit option is selected.
Profile Changes In Mass	RUN_AMPRFCHG	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Profile Changes In Mass	Copy an asset profile from one SetID to another, or update a profile by changing some of its attributes.

Understanding Asset Profiles

An *asset profile* is a template that contains standard depreciation criteria for an asset type and its corresponding asset books. The information established in an asset profile can be used as default values when you're adding assets to the system. Profiles associated with indexes enable replacement cost calculations. Profiles are recommended when you have a large number of assets of the same type. Defining default values minimizes data entry, ensures consistency, and enhances accuracy levels.

Set up asset profiles to match most, if not all, of the major asset categories that you track on your books. These can range from the standard categories such as Land, Furniture & Fixtures, Machinery & Equipment, and Expensed Items, to more detailed categories that you may want to track, such as Computers, Software, Phones, and Fax Machines.

Note: You must set up at least one asset profile before you can add any assets to the system. Remember that profiles are templates that help reduce data entry when you are actually adding an asset. When you go through the process of entering assets into the system, you can override any of the fields in an asset profile. Because profiles are required when you are using ExpressAdd, Oracle recommends that you set up a blank dummy profile for nonstandard assets.

Asset Profiles – Definition Page

Use the Asset Profiles - Definition page (PROFILE_DEFN) to define asset profiles.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Profiles, Asset Profiles

Image: Asset Profiles - Definition page

This example illustrates the fields and controls on the Asset Profiles - Definition page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Profile' definition page with the following fields and controls:

- SetID: SHARE, Profile ID: AUTO
- Description: Automobile
- Asset Description: Automobile
- Asset Class: (lookup icon)
- *Asset Type: Fleet (dropdown)
- Acquisition Code: Purchased (dropdown)
- Asset Subtype: (lookup icon)
- Capitalized Asset:
- Use NBV for R and D:
- R and D Plant Asset:
- Taggable Asset:
- Use As Tool:
- Asset Retirement Obligations:
- R and D Start Date: (calendar icon)
- SubIndex Name: AUTOMOBILES (lookup icon)
- Index Name: CPI (lookup icon)
- Threshold ID: (lookup icon)

Below the fields is a table with the following data:

Book Name	Description	Dgpreciation	Tax	Parent/Child
CORP	Corporate	Dgpreciation	Tax	Parent/Child
FEDERAL	Federal	Dgpreciation	Tax	Parent/Child

You create asset profiles from the Profile (PROFILE) component. You can create profiles with varying levels of detail. The level that you use depends on how much information you want to be provided by default into the system when you add an asset. Some asset profiles are used to define financial attributes, while others are not. To successfully create a financial profile, you must enter at least the following information:

- Profile ID.
- Asset category.
- Asset book name.
- Depreciation attributes.
- Asset type.

Each profile has a unique profile ID. You can use this ID to group profiles by type. For example, you might want to have several automobile profiles, such as *Autos*, *Autos-Luxury*, and *Autos-Leased*.

Asset Description	Enter a description for this asset profile.
Asset Class	Select the asset class with which an asset profile will be associated by default. The available options are defined when you establish asset class codes.
Asset Type	Select the asset type. Oracle delivers these asset types: <i>Hardware, Software, Equipment, Property, Fleet, Machinery, Furniture, Facility, Intangible, Other</i> .
Asset Subtype	Select the asset subtype. Valid values for the selected asset type appear from the drop-down list box.
Acquisition Code	Select the acquisition code from the drop-down list box. Available options are: <ul style="list-style-type: none"> • <i>Construct</i> • <i>Donated</i> • <i>Leased</i> • <i>Like Exch</i> (like exchange) • <i>Purchased</i> • <i>Trade In</i> • <i>Transfer</i>
Taggable Asset	Select to indicate that an asset is taggable. Most physical assets can be tagged with a tag number to help keep track of them. Some assets, however, such as buildings or leasehold improvements, cannot be tagged. If an asset is taggable, it probably already has a tag number associated with it, which is recorded when the asset is added. Sometimes, however, an asset may be taggable, but not yet tagged. The Taggable Asset check box can be used to flag this type of asset.

Note: To use the Physical Inventory functionality in PeopleSoft Asset Management, your assets must be tagged.

Capitalized Asset

Select to indicate whether this profile will be used for assets with cost and depreciation associated with them. Most assets in the PeopleSoft Asset Management system will be capitalized assets. If you are setting up a profile for noncapitalized assets, (assets with no cost or depreciation criteria), deselect Capitalized Asset. Typically these assets are expensed, not actually owned, or fully depreciated, but you still want to track them.

Use As Tool

Select if the asset is used as a tool in connection with the maintenance or repair of another asset.

Asset Retirement Obligations

Select this option for an asset profile to apply asset retirement obligation (ARO) defaults to the associated asset, thus flagging the asset as eligible for ARO processing. You can select the Asset Retirement Obligation check box for any asset profile to apply ARO defaults when adding an asset. If you decide that the asset is not ARO-eligible, you can deselect the defaults for the asset manually when adding it. Conversely, if you do not use an asset profile, or the selected profile does not carry the ARO defaults, you can manually select the ARO options for the asset when adding it in the Basic Add component. to be used specifically as default profiles for assets requiring ARO treatment when you add new assets. The ARO functionality provides asset retirement obligation measurement and reporting in compliance with Financial Accounting Standards for leased assets, group assets, and asset impairment.

See "Understanding Adding and Maintaining Assets (*PeopleSoft FSCM 9.2: Asset Management*)"

For more information, see "Accounting for Asset Retirement Obligations (*PeopleSoft FSCM 9.2: Asset Management*)"

Index Name

Select the index by which replacement or valuation cost will be calculated. When you run the Calculate Replacement Cost (AMRCCALC) process, it multiplies the asset cost by the amount in the index selected here.

SubIndex Name

Select the subindex category for the index to use to calculate replacement or valuation cost.

Threshold ID

Select the Threshold ID to be used as the default value for assets within a given profile when using the optional Capitalization Threshold feature. Capitalization thresholds are defined on the Capitalization Thresholds page and selected at the asset profile level.

When the Capitalization Threshold feature is enabled, PeopleSoft Asset Management:

- Automatically catalogues the capitalization status for batch and online asset additions.

- Provides processes to deal with adjustments to the original cost.
- Balances out any potential clearing account with other feeder systems.
- Reassesses the capitalization status of the asset when subsequent transactions occur.
- Provides reports and audit trails to facilitate control of these transactions.

When adding an asset, the system uses the capitalization definition for the applicable Threshold ID to determine the appropriate capitalization action to take. Upon saving, the system compares the asset cost with the cost established for each bracket, as well as the basis option to decide the appropriate action to take. Alternatively, you can select to have the capitalization analysis performed by unit cost rather than total cost.

Note: This field appears only when the Capitalization Threshold feature has been enabled from the Asset Management Installation Options page.

See [Capitalization Thresholds Page](#).

(AUS) Using Research and Development Information

Research and Development Information is used to meet Australian asset processing requirements; for others, these fields are informational.

R and D Plant Asset (research and development plant asset)

Select if this asset is being used for research and development and is entitled to R&D tax concessions.

R and D Start Date (research and development start date)

Enter the date on which the asset was first used exclusively for R&D. If you leave this field blank, the in-service date from the tax book of the business unit will be used as the start date. The start date determines in what year the R&D concessions can first be claimed.

Use NBV for R and D (use net book value for research and development)

Select if you want to base the R&D concessions calculation on the net book value of the asset (at the R&D start date) instead of the book cost. This is useful when an asset previously being depreciated as a non-R&D asset subsequently becomes eligible for R&D concessions.

See "(AUS) Using PeopleSoft Asset Management Options to Meet Australian Requirements (*PeopleSoft FSCM 9.2: Asset Management*)".

Asset Profiles - Depreciation Page

Use the Asset Profiles - Depreciation page (PROFILE_BK_01) to identify the criteria to use in depreciation calculations.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Profiles, Asset Profiles, Depreciation

Image: Asset Profiles - Depreciation page

This example illustrates the fields and controls on the Asset Profiles - Depreciation page. You can find definitions for the fields and controls later on this page.

The screenshot displays the 'Depreciation' tab of the 'Asset Profiles - Depreciation' page. The page is organized into several sections:

- Book Information:** SetID (SHARE), Profile ID (AUTO), Automobile. Book Name (CGRP), Corporate, Country (USA).
- Depreciation Attributes:**
 - Effective Date: 01/01/1900
 - Category: Automobile
 - Currency Code: USD (US Dollar)
 - Convention: Following Month
 - Retire Conv: Following Month
 - Depreciate When In Service:
 - Depr Status: Depreciable
 - Adjust Conv: Actual Month
 - Retire Option: Calculate Gain/Loss
- Method and Calculation:**
 - *Method: Straight Line
 - Calculation Type: Life-to-Date
 - Percent:
 - Limit Pct:
 - Useful Life: 60
 - Schedule:
 - UOP ID:
 - End Date:
 - Low Limit: Monthly:
 - DB Pct: Low Value:
 - Method ID: Depr Pass Life:
 - Avg Option: No Averaging
 - Future Depr Yrs:
- Special Depreciation:** Special Depreciation
- Special Terms:**
 - Depr Limit:
 - Salvage % of Cost:
 - Multi-Shift Code:
 - Group BU:
 - Cost Basis Limit:
 - Salvage: 2000.00
 - Salvage Rounding:
 - Group ID:
 - Impairment Process

Note: Each asset can report to multiple books and have multiple depreciation attributes per book.

Book Name

Enter a book name that defines the rules for the assets entered with this profile. Books are defined during system setup and associated with business units. Only valid books can be assigned.

Effective Date

Enter the date that indicates when the convention and depreciation method take effect. If you want a history of changes made to a profile, be sure to add new rows to the table and use effective dating to update profiles, rather than making changes to the initial row.

Depreciate When in Service

Select to allocate annual depreciation as of the date that you placed the asset in service. If you do not select this option, PeopleSoft Asset Management allocates annual distribution as of the date determined by the depreciation convention. This option is valid only in the year that the asset was acquired.

Category

Defines the category of an asset, such as Furniture & Fixtures or Machinery & Equipment. The available category codes are those you entered on the Category Code table. In general, these will correspond to the General Ledger asset accounts. Asset Category is used in accounting entry generation.

Depr Status

Enter the depreciation status.

Currency Code

Select a currency code.

Adjust Conv (adjustment convention) Select an adjustment convention.

Convention

Select a depreciation convention.

Retire Conv

Select a retirement convention.

Retire Option

Select the retirement calculation option to be processed for assets within a given profile. These retirement options are available at the profile, book and asset levels.

See "Retire Assets Page (*PeopleSoft FSCM 9.2: Asset Management*)".

Method

Select a depreciation method. Some depreciation methods require you to enter additional information.

Note: If you specify the depreciation method as Flat Rate or a Declining Balance method or Manual depreciation for tax books, you should enter the recovery life.

Note: If you select Non Depreciable on this page, you must still enter values for Useful Life and Convention. However, you need not update the remainder of the Asset Profiles pages. Because the profile is defined for nondepreciable assets, the information in these pages will not be used in any processing.

Ensure that you establish an effective date for the profile that is valid for the currency code specified for the profile.

Method	Fields That Appear
<i>Declining Balance w/SL by Limit %</i>	DB Pct (declining balance percent) and Limit Pct
<i>Declining Balance</i>	Percent, Low Limit, Monthly
<i>Declining Balance w/SL</i>	DB Pct
<i>Depreciation Schedule</i>	Schedule

Method	Fields That Appear
<i>Flat Rate %</i>	Percent, Low Limit, Avg Option (averaging option)
<i>France Derogatory Balance</i>	DB Pct Percent, Low Limit, Depr Pass Life (depreciate past life)
<i>Germany Staffel Method</i>	DB Pct, Percent, Low Limit, Depr Pass Life
<i>Japan – Lease Depreciation</i>	No additional fields appear.
<i>Japan – Intangible/Strt Line</i>	DB Pct, Percent, Low Limit, Depr Pass Life
<i>Japan – Tangible / Declining Bal</i>	DB Pct, Percent, Low Limit, Depr Pass Life
<i>Japan – Tangible/Strt Line</i>	DB Pct, Percent, Low Limit, Depr Pass Life
<i>Japan – Changes DB to SL</i>	DB Pct, Percent, Low Limit, Depr Pass Life
<i>Japan - Changes DB to SL Rev</i>	DB Pct, Percent, Low Limit, Depr Pass Life Available for assets acquired on or after April 1, 2007.
<i>Japan - Tangible / Strt Line Rev</i>	DB Pct, Percent, Low Limit, Depr Pass Life Used for assets acquired on or after April 1, 2007.
<i>Manual Depreciation</i>	No additional fields appear. The Manual Depreciation method enables you to adjust depreciation amounts that are generated by some other method. To use manual depreciation, you must therefore first create depreciation entries using another method. When this has been done, you can make your adjustments.
<i>Straight Line</i>	Useful Life
<i>Straight Line Percent</i>	(IND) Percent
<i>Sum of the Years</i>	NA
<i>Units of Production</i>	UOP ID (units of production ID)
<i>User Defined Method</i>	Method ID, DB Pct, Percent, Low Limit, Depr Pass Life

The following table defines the additional fields:

Limit Pct (limit percent)	Enter a limit for depreciation as a percentage of cost.
UOP ID (units of production ID)	Enter the units of production ID, production information, and transaction information that you want to use for this asset.
DB Pct (declining balance percent)	Enter the percentage of declining balance depreciation to be taken each year until the amount calculated by the straight line method is greater.

Percent	Enter the percentage of original basis to be taken in depreciation each year. This is required for straight line percent.
Low Limit	Enter an amount. When the asset basis reaches this limit, the remaining basis will be taken in depreciation and the asset will be fully reserved.
Depr Pass Life (depreciate past life)	Select if you want to continue to depreciate this asset past its useful life end date. This option is used for governmental regulations for certain countries or for utilities industries that may want to continue to depreciate an asset to the end of a depreciation calendar.
Method ID	Select the user-defined method that you want to use.
Schedule	Enter a schedule to use for depreciation.
Avg Option (average option)	<p>Generally used by utility companies to depreciate composite assets. The averaging options are expressly designed to work with the flat rate depreciation method. Select an averaging option if you want to use it:</p> <p><i>Monthly:</i> Monthly averaging takes an average monthly asset balance and multiplies it by the annual depreciation rate. The result is then applied against a period allocation (1/12, 2/12, 3/12, and so on) to derive a year-to-date (YTD) depreciation amount. The difference between the newly calculated YTD depreciation and the previous YTD depreciation is the amount booked to the current period.</p> <p><i>Yearly:</i> Yearly averaging is similar to monthly averaging except that a yearly average balance is used. Because this amount is not known until the end of the year, it is usually estimated and adjusted periodically as the actual figures become known.</p>

Note: Using the flat rate depreciation method will cause any depreciation to be posted to the end of the calendar. If this is not your intention, you must enter a low limit of *.01* when you first select the depreciation method for this asset. If you have not already done this, update the Depreciation Method field by selecting *Flat Rate* and entering *.01* in the Low Limit additional field that appears.

Calculation Type	<p>Select the calculation type.</p> <ul style="list-style-type: none"> • Use <i>Remaining Value</i> to deduct any accumulated depreciation from the cost basis and expense the remaining value over the remaining life of the asset. Most assets will be depreciated using this option. • Use <i>Life-to-Date</i> to calculate the difference between the depreciation allowed and the depreciation taken. Typically, you would use life-to-date calculations when a change occurs in accounting principle, such as depreciation
-------------------------	----------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------

method. Changes of this type require an adjustment for the differences in accumulated depreciation to date.

For example, if you took 20,000 USD depreciation over a two-year period but the amount allowed was \$24,000, the difference of \$4,000 would be expensed as an adjustment to accumulated depreciation in the current period.

Low Value	Select to identify assets with costs below a certain level for special depreciation processing. This is a requirement for some countries.
Useful Life	Enter the number of periods. This is used to perform the depreciation calculations for the financial books.
End Date (end depreciation date)	Enter an end date that you want depreciation to cease at a particular time. At the end depreciation date, the remaining asset basis will be taken in depreciation and the asset will be fully reserved.
Future Depr Yrs (future depreciation years)	PeopleSoft Asset Management calculates and stores depreciation until the end of the asset life. However, for optimal processing performance and greater table efficiency, you can specify a fixed number of years for which depreciation is calculated and stored.
<hr/>	
Note: Oracle strongly recommends using the Future Depreciation Years option if you are using group assets.	
<hr/>	
Special Dpr (special depreciation)	Select if you are working in a global environment and want to use special depreciation terms to meet specific country requirements. Click Special Terms to open the Depreciation Method Information page, where you can select special terms for depreciation.
Depr Limit (depreciation limit code)	Select a depreciation limit code that relates to a specific dollar amount limitation on depreciation for each year of life. Although this can be used for financial depreciation, it is commonly used for U.S. tax purposes, because such depreciation limits exist for items such as luxury automobiles.
Cost Basis Limit	Enter the limit on the depreciable basis of this asset. If the actual cost of an asset is greater than its depreciable basis, the difference will result in a gain when the asset is retired.
Impairment Process	Select to make the asset available for impairment processing.
Salvage % of Cost and Salvage	Enter the residual value of the asset subtracted from the cost to determine the depreciable basis used in depreciation calculations. You can enter it either as a flat rate or as a salvage percentage (a percentage of the total cost of the asset). If you use a salvage percentage, the system recalculates the salvage value when you add additional costs for the asset.

- (DEU) Multi-Shift Code** Enter rates by which depreciation should be increased based on the number of production shifts that an asset is used. This is used in Germany.
- Group BU** Enter the business unit for the group assets.
- Group ID** Select the group ID.

Note: Each group member asset profile can be used by only one business unit.

Depreciation Method Information Page

Use the Depreciation Method Information page (PROFILE_DEPR_DETL) to set special depreciation terms for an asset profile and select an accounting method for these special terms.

These are commonly used to meet depreciation requirements for specific countries.

Navigation

Select the Special Depr check box and click Special Terms on the Depreciation page of the Asset Profile component.

Image: Depreciation Method Information page

This example illustrates the fields and controls on the Depreciation Method Information page. You can find definitions for the fields and controls later on this page.

- Allowance** Select to specify that special depreciation amounts are not booked with the standard depreciation amounts. Journal entries

are generated that will include only the standard depreciation. PeopleSoft Asset Management does not support automatically generating journal entries for the special depreciation allowance accounting method. You may need to run two reports: Reserve for Special Depreciation and Reversal for Special Depreciation, and then generate the journal entries manually into the PeopleSoft General Ledger system.

Expense

Select to specify that total amounts of special depreciation and standard depreciation are booked and journal entries are generated that will include the total of standard and special depreciation amounts.

Reserve

Select to specify that special depreciation amounts are not booked with the standard depreciation amounts. Journal entries are generated that will include only the standard depreciation. PeopleSoft Asset Management does not support automatically generating journal entries for the special depreciation allowance accounting method. You may need to run two reports: Reserve for Special Depreciation and Reversal for Special Depreciation, and then generate the journal entries manually into the PeopleSoft General Ledger system.

Note: Additional fields are provided to comply with the depreciation methods used in countries other than the U.S.

When you use additional terms, they affect depreciation calculations in the following ways:

<i>Term</i>	<i>Depreciation</i>
Special	Depreciation × Rate
Accelerated	Depreciation × Rate
Initial	Cost × Rate
Increase	Depreciation × Rate

Note: Year of Change(displayed from the ASSET_DPR_DETAILS page) is available only when the depreciation method is *Japan-Change DB to SL*.

(ARG, BRA, and MEX) Asset Profiles - Inflation Information page


Use the Asset Profiles - Inflation Information page (PROFILE_SEC) to establish an inflation adjustment factor by selecting the market index and rate to apply.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Profiles, Asset Profiles, Depreciation, Inflation Information

Image: Asset Profiles - Inflation Information page

This example illustrates the fields and controls on the Inflation Information page. You can find definitions for the fields and controls later on this page.



- Market Rate Index** Select the market rate index to be used for inflation processing.
See "Defining Market Rates (*PeopleSoft FSCM 9.2: Global Options and Reports*)".
- Rate Type** Select the market rate type to be used for inflation processing.
- Term** Select the term.
- Daily Rate Index** Select the daily rate index.
- Daily Rate Type** Select the daily rate type.
- Daily Term** Select the daily term.
See "Establishing Market Rates (*PeopleSoft FSCM 9.2: Global Options and Reports*)".

(JPN) Salvage Rounding Options page

Use the Salvage Rounding Options page (SALVAGE_OPTION_SEC) to enter options for rounding depreciation amounts for this book.

This is for use in Japan.

Navigation

Click Salvage Rounding Options on the Asset Profile - Depreciation page.

Image: Salvage_Rounding_Options

This example illustrates the fields and controls on the Salvage_Rounding_Options. You can find definitions for the fields and controls later on this page.

Rounding Rule

The rounding rules that are delivered with PeopleSoft Asset Management are:

Down

NatRnd

Up

Round Type

The rounding types that are delivered with PeopleSoft Asset Management are:

Currency

Generic

Rounding Precision

Enter the number of places to the right or left of the decimal point to which the amount or number will be rounded. If you select *Currency* as the round type, the system automatically determines the round precision from the currency code.

Rounding Factor

Enter the number to which the amount will be rounded. For example, if you select *Nat Rnd* as the rounding rule, and enter a rounding factor of 25, amounts will be rounded to the nearest multiple of 25 so that an amount of 130 will be rounded to 125, and an amount of 140 will be rounded to 150. If you select

Currency as the round type, the system will automatically determine the rounding factor from the currency code.

Truncation Precision Flag

Works with the round precision value. When you select it, amounts that contain many decimal places will be truncated to one decimal place to the right of the rounding precision position before rounding is performed. If you do not select it, the entire amount will be rounded. This example illustrates truncation precision:

- Amount to be rounded: 10.03439.
- Round precision: 3.

With Truncation Precision Flag selected, the system truncates the fifth decimal place and rounds 10.0343. Without the check box selected, the system rounds the entire amount. Actual rounding results depend on the selected rounding rule and round type.

See "Understanding PeopleSoft Asset Management in Global Settings (*PeopleSoft FSCM 9.2: Asset Management*)".

Asset Profiles - Tax Page

Use the Asset Profiles - Tax page (PROFILE_BK_03) to specify property type and tax depreciation criteria and identify which tax credits will be used by the profile.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Profiles, Asset Profiles, Tax

Image: Asset Profiles - Tax page

This example illustrates the fields and controls on the Asset Profiles - Tax page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Tax' tab of the 'Asset Profiles' page. At the top, there are tabs for 'Definition', 'Depreciation', 'Tax', and 'Child Asset Inheritance'. Below the tabs, there are search and navigation controls for 'Book' and 'Tax'. The 'Book' section shows 'Book Name' as 'CORP' (Corporate) and 'Country' as 'USA'. The 'Tax' section contains several fields: 'Effective Date' (01/01/1900), 'Business Tax' (checkbox), 'Property Type' (Personal), 'Property Code' (1245), 'Regulation', 'Recovery Life', 'Recovery SubType', 'Guideline Class', 'Corporation Sec.291' (checkbox), 'Listed Property' (checkbox), 'Listed Property Type', 'Business Use %', 'Depreciation Bonus' (None), and 'Bonus Percent'. At the bottom, there is a 'Tax Credit Options' table with columns for 'Qualified Investment Code', 'Tax Credit Type', 'Tax Credit Code', and 'Basis Reduction Option'. The table has one row with the value '1' in the first column.

Note: Asset tax attributes primarily address Unites States tax issues except where noted.

Property Type and Property Code	Determine the amount of gain treated as ordinary income on the disposition of this asset.
Regulation	Identifies the depreciation system elected for this asset: <ul style="list-style-type: none"> • Accelerated Cost Recovery System (ACRS). • Asset Depreciation Range (ADR). • Conventional/Facts & Circumstance. • Asset Class Guideline. • Modified Accelerated Cost Recovery (MACRS).
Recovery Life and Recovery Subtype	For reporting purposes, you can further classify the asset by specifying the recovery life expressed in years and the recovery subtype, for example, <i>15-Year Low-Income Housing</i> . You can also specify the asset guideline class. All current classifications are set up in the Tax Class table in the delivered tableset.
(IND) Guideline Class	Processing tax and depreciation in India requires the designation of a tax class rate that is associated with an asset block. To associate the tax class rate with a profile, enter the tax class and associated asset block rate here.
Corporation Sec. 291 (corporation section 291)	Select if this company is a corporation. This check box must be selected if the company is a corporation for the AMTX3210 tax report (Tax Retirement Capital Gains) to accurately reflect the correct Sec. 1231/Ordinary gains.
(FRA) Business Tax	Select if assets using this profile are subject to a business tax. This is required in some countries.
Listed Property	Select to record whether the asset is listed property. Listed property is a certain kind of asset that is conducive to mixed business or personal use, such as: <ul style="list-style-type: none"> • Passenger automobiles under a certain weight. • Any other property used for transportation, such as trucks, buses, boats, airplanes, motorcycles, and any other vehicles for transporting persons or goods. • Any property of a type generally used for entertainment, recreation, or amusement, such as photographic, phonographic, communication, and video recording equipment. • Any computer and related peripheral equipment, unless it is used only at a regular business establishment and owned or leased by the person operating the establishment.

- Any cellular telephone (or similar telecommunications equipment) placed in service or leased in a tax year beginning after 1989.

Listed Property Type

Select the property type that corresponds to the Listed Property check box.

Business Use % (business use percentage)

Enter the percentage amount of the business use of this listed property asset. Based on the business use percentage that you enter, the basis calculated for depreciation is:

$$(Basis) = (Cost * Bus_Use_%)$$

(USA) Depreciation Bonus

Select to indicate the specific depreciation bonus definition if the asset qualifies for depreciation bonus treatment. You can also create your own depreciation bonus definitions for selection in this field using the Depreciation Bonus Info page.

See [Defining Depreciation Bonus Information](#).

PeopleSoft delivers the following values:

- *American Recovery*: Select if the qualifying asset is placed in service on or after January 1, 2009 and on or before December 31, 2009 (before 2010 for certain transportation property and certain property with a long production period).
- *Gulf Opportunity Zone*: Select for certain types of assets that are located within the hurricane zone as defined in the Senate Amendment to H. R. 4440 and the acquisition date and in-service date are on or after August 28, 2005 and on or before December 31, 2007 (December 31, 2008 for nonresidential real property or residential rental property).
- *New York Liberty Zone*: Select if the acquisition date and in-service date are on or after September 11, 2001 and on or before December 31, 2007.
- *None*: Select if the acquisition date and in-service date of the asset are on or before September 10, 2001, or, if the other options do not apply.
- *Section Federal (50%)*: Select if the acquisition date and in-service date are after May 5, 2003 and on or before December 31, 2005 to apply the 50 percent bonus.
- *Section 101- Local*: Select if local or state allowance of the bonus depreciation should be applied. Define the parameters of the bonus depreciation as according to applicable local or state law using the Depreciation Bonus Info page.
- *Small Business Jobs*: Select if the qualifying asset is placed in service on or after January 1, 2010 and on or before

December 31, 2010 (before 2011 for certain transportation property and certain property with a long production period).

- *Stimulus Act*: Select if the qualifying asset is placed in service on or after January 1, 2008 and on or before December 31, 2008 (before 2010 for certain transportation property and property with a long production period).

(USA) Bonus Percent

Supply the amount (percentage) to be applied if the asset qualifies for a depreciation bonus based on the acquisition date and in-service date.

Using Tax Credit Options

The rate and amount of the tax credit are based on federal tax law and determined by the qualified investment code, tax credit type and code, and basis reduction option in PeopleSoft Asset Management.

Select a qualified investment code if applicable:

A (accelerated):	Accelerated Cost Recovery System (ACRS)
D (depreciation):	Asset Depreciation Range
F (facts):	Conventional Facts and Circumstances
G (guidelines):	Guideline
M (modified):	Modified Accelerated Cost Recovery (MACR)

Select a tax credit type if applicable. In the U.S., certain business incentive credits can be taken:

R (rehabilitation):	Rehabilitation Credit
E (energy):	Energy Credit
I (investment):	Regular Investment Credit
U (user):	User-defined

The tax credit code further defines the tax credit. For example, a 20 percent rehabilitation tax credit is available for historic buildings. Some credits require a corresponding reduction in the cost basis of the asset.

The basis reduction option indicates whether a reduction in the cost basis is required. Three codes are provided:

B (basis):	Basis Reduction
P (percentage):	Percentage Rate Reduction
N (no):	No Reduction

Related Links

"Understanding PeopleSoft Asset Management in Global Settings (*PeopleSoft FSCM 9.2: Asset Management*)"

Child Asset Inheritance Page

Use the Asset Profile - Child Asset Inheritance page (PROFILE_PAR_BK_ECD) to specify child asset attributes that will be used by the profile and inherited from the parent asset for Express Add, Basic Add, and batch-created assets.


The inheritance based on the selected items happens upon defaulting the profile in Express Add and capitalizing the asset in Basic Add, and when you are using Default Profile processing in the Transaction Loader if the Business Unit option is selected.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Profiles, Asset Profiles, Child Asset Inheritance

Image: Asset Profiles - Child Asset Inheritance page

This example illustrates the fields and controls on the Asset Profiles - Child Asset Inheritance page. You can find definitions for the fields and controls later on this page.



Select the attributes and other information that the child asset inherits from the parent asset.

Related Links

"Adding and Maintaining Asset Information (*PeopleSoft FSCM 9.2: Asset Management*)"
[Understanding Asset Management Business and Cash Generating Units](#)

Establishing Asset Ownership

To establish asset ownership, use the Define Asset Owners (AM_OWNER_COMP) component.

To set up an asset owner user, use the Assign Owners to Operators (AM_OWNER_OPR_COMP) component.

This topic provides an overview of asset ownership and discusses how to:

- Define asset owners.
- Assign users to owners.
- Define asset owner users.

Pages Used to Establish Asset Ownership

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Asset Owner	AM_OWNER_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Define Asset Owners	Define role-based asset owners and assign assets to the owner based on ChartField and other attributes.
Asset Owner User	AM_OWNER_DEFN2	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Define Asset Owners, Asset Owner User	Assign operators to owners.
Setup Asset Owner User	AM_OWNER_OPR_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Assign Owners to Operators	Define role-based owner users.

Understanding Asset Ownership

PeopleSoft Asset Management uses a concept called *asset ownership* in which a relationship is established between assets, ChartField combinations, asset category, asset type, asset location, asset manufacturer or model, or asset department and the individuals who have responsibility for managing them. Asset owners might be plant managers, store managers, or department heads and each owner can be associated with multiple asset operators, such as plant engineers, store clerks, and department workers.

An asset ownership definition provides a manager or supervisor discrete visibility into the transactions affecting the assets for which she is responsible and enables the express retirement of those assets by means of the Asset Management Disposal Worksheet. The disposal worksheet automates the retirement process between the asset owner and the property accounting personnel that are responsible for completing the financial transactions relative to the assets themselves, including the optional establishment of a role-based approval process. The owner-to-operator definition may optionally authorize operator access to asset cost history data and disposal approval.

Asset Owner Page

Use the Asset Owner page (AM_OWNER_DEFN) to define role-based asset owners and assign assets to the owner based on ChartField and other attributes.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Define Asset Owners

Image: Asset Owner Page

This example illustrates the fields and controls on the Asset Owner Page. You can find definitions for the fields and controls later on this page.

*Field Name	*Field Value	*To Value
1 Asset Category	BLDG	BLDG

Select the role to be defined as the asset owner.

Asset Selection Attributes

Using the drop-down search keys, select the field name to use to establish ownership.

For example, the manager may be responsible for all assets in Department 11000 through, Department 12000, Location Sydney, and Category Computer Items. Select *Department* and define the range of field values, select *Location* and define the location field value of Sydney, and select *Category* and define the category field value of Computers.

Asset Owner User Page


Use the Asset Owner User page (AM_OWNER_DEFN2) to assign operators to owners.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Define Asset Owners, Asset Owner User

Image: Asset Owner User page

This example illustrates the fields and controls on the Asset Owner User page. You can find definitions for the fields and controls later on this page.



Asset Owner User

Link the asset owner to users or operators. Under User ID, enter the user IDs that are assigned to the asset owner.

Select Retire Approval Required to indicate that an approval step is required prior to asset disposal.

Select Show Cost to indicate whether the user ID will have access to cost information in the express retirement pages.

Asset Owners to Operators Page

Use the Setup Asset Owner User page (AM_OWNER_OPR_DEFN) to define role-based owner users.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Assign Owners to Operators

Image: Assign Owners to Operators page

This example illustrates the fields and controls on the Assign Owners to Operators page. You can find definitions for the fields and controls later on this page.

Setup Asset Owner User				Personalize	Find	[?]	[grid icon]	First	1-3 of 3	Last
*User ID	*Asset Owner	Retire Approval Required	Show Cost							
1 VP1	MANAGER	<input type="checkbox"/>	<input checked="" type="checkbox"/>							
2 VP2	SUPERVISOR1	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>							
3 VP3	SUPERVISOR2	<input checked="" type="checkbox"/>	<input type="checkbox"/>							

The Asset Owner User page enables you to make assignments owner by owner. The Setup Asset Owner User page enables you to you add multiple operators and owners at one time.

Setup Asset Owner User

Assign user ID to asset owner and set up retire approval required, and show cost options for each user ID.

Note: A warning appears if the Retire Approval Required and Sow Cost options that are established here for a user ID are in conflict with those established in the Asset Owner User page (AM_OWNER_DEFN2).

Defining On-Demand Processing for PeopleSoft Asset Management

To set up on-demand processing options, use the On-Demand Process Options component (RTM_OPTIONS).

This topic provides an overview of on-demand processing and lists the page used to define on-demand processing for PeopleSoft Asset Management.

Page Used to Define On-Demand Processing

Page Name	Definition Name	Navigation	Usage
On-Demand Processing Options	RTM_OPTIONS	Set Up Financials/Supply Chain, Common Definitions, On-Demand Processing, On-Demand Process Options	Define the process groups that certain users can run on demand.

Understanding On-Demand Processing for PeopleSoft Asset Management

Process groups are groups of processes that certain users can run on demand, directly from transaction entry pages, such as the Invoice Information page in the Voucher component of Payables. The process groups that are available depend on your user ID and whether a given transaction requires the processing.

Before you can use on-demand processing, you must specify the accounting entry definitions that will be used by each source transaction-process group combination, along with other options. Accounting entry definitions define the record and fields that the Journal Generator process uses to extract accounting entries from the system source.

Set up on-demand processing for:

- INTFAPAM: AP/AM Interface Application Engine.
- AMPS1000: Preinterface loader.
- AMIF1000: Transaction loader.

Setting Up Reporting Options

This topic provides an overview of reporting options and discusses how to:

- Establish drill-down field groups.
- (Optional) Link field group IDs to user IDs.
- Set up report suffix.
- Add report format templates.

Pages Used to Set Up Reporting Options

Page Name	Definition Name	Navigation	Usage
Reporting Drilldown Fields	RPT_DRILL_FLD_G	Set Up Financials/Supply Chain, Product Related, Asset Management, Reporting Setup, Reporting Drilldown Fields, Reporting Drilldown Fields	Define the drill-down group ID and select drill-down fields.
User Preferences - Asset Management	OPR_DEF_TABLE_AM1	Set Up Financials/Supply Chain, Common Definitions, User Preferences, Define User Preferences, Asset Management	Select a drill-down group to associate with this user ID.
Report Suffix	REPORT_SUFFIX	Set Up Financials/Supply Chain, Product Related, Asset Management, Reporting Setup, Report Suffix	(Required) Denotes the Report By value for the report, appended to the report ID to uniquely identify it. The default sort order is ChartField, (CF).

Page Name	Definition Name	Navigation	Usage
ChartField Format Template	RPT_FMT_TMPL_SBP	<p>Access the run control page for the report to be formatted with user-defined parameters and expand the Report Print Options group box.</p> <p>Click the Update/Add CF Template link in the Report Print Options group box from certain Asset Details and Cost and Depreciation Reports.</p>	Update or add new ChartField report formats.
Report Fields Format Template	RPT_FMT_TMPL2_SBP	<p>Access the run control page for the report to be formatted with user-defined parameters and expand the Report Print Options group box.</p> <p>Click the Update/Add RF Template link in the Report Print Options group box from certain Asset Details and Cost and Depreciation Reports.</p>	Update or add new report field formats.

Understanding Reporting Options

Oracle delivers several kinds of report options within PeopleSoft Asset Management.

Online Drill-Down Options

Online reporting enables users to view details of costs and depreciation from high-level summary views to the lowest reporting level available for reporting periods.

PeopleSoft Asset Management provides online inquiries of the depreciation reporting table (DEPR_RPT) displaying high-level summary data for a period with details available through drill-down functions, defined at the business unit and book definition level. When enabled for online reporting, selection criteria includes business unit, book, fiscal year, period, asset category, profile ID, and ChartFields. The drill-down feature provides the option to view the data presented to the lowest level available.

Report Format Template and Suffix

Most of the reports that are used for different functions within PeopleSoft Asset Management make use of the same data but report it from a different perspective. For example, depreciation is often reviewed by ChartField activity. However, reviewing depreciation based on a category or location is also useful. To that end, you can use a report template that enables you to define the reporting-by method to be used.

Oracle delivers a report template that all users can share but that you can define to include or exclude information of your choosing. The template controls the report title, Report By field name, sort order, field length to display, field label overrides, amount field length, and subtotalling. To accommodate the varying needs of many users, the report can be generated using Report By as the key, with a report suffix added to the report ID to indicate what value is used for Report By.

PeopleSoft Asset Management also provides the tools to produce reports in user-defined formats. With report IDs or user IDs as keys to reporting templates, multiple groups or individuals use the same general

information provided in a report but receive it in a dynamically defined format addressing the particular needs of the group or individual.

Reporting Drilldown Fields Page

Use the Reporting Drilldown Fields page (RPT_DRILL_FLD_G) to define the drill-down group ID and select drill-down fields.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Reporting Setup, Reporting Drilldown Fields, Reporting Drilldown Fields

Detail View

Select the corresponding check box for each field that you want available for drilldown. Clear any fields to be excluded. For example, if your organization does *not* track anything by class, a column for the field will appear on your report, but no values will appear. To remove the column from a report, deselect the check box on this page.

(Optional) User Preferences - Asset Management Page

Use the User Preferences - Asset Management page (OPR_DEF_TABLE_AM1) to select a drill-down group to associate with this user ID.

Navigation

Set Up Financials/Supply Chain, Common Definitions, User Preferences, Define User Preferences, Asset Management. Select a user ID.

Field Drilldown Group Id

Select the group ID to associate with this user ID. If you do not select a group ID, all fields are available for drilldown. The drill-down field list could be very long. To create a drill-down list that is more specific, you can drill down by project ID and department ID only, thereby reducing the list using this setup.

Report Suffix Page

Use the Report Suffix page (REPORT_SUFFIX) to (Required) Denotes the Report By value for the report, appended to the report ID to uniquely identify it.

The default sort order is ChartField, (CF).

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Reporting Setup, Report Suffix

Enter the values to be appended to the report ID, which identify the name of the available field by which the report is run. For example, the report, Depreciation Activity by ChartField, uses the report ID AMDP2000. When you report by department, the report suffix 5 is appended to the report ID, which then appears as AMDP2000-5. This means that the report contents are presented in department order. As you add or change ChartFields, you must add or change the corresponding values in this list.

ChartField Format Template Page

Use the ChartField Format Template page (RPT_FMT_TMPL_SBP) to update or add new ChartField report formats.

Navigation

Access the run control page for the report to be formatted with user-defined parameters and expand the Report Print Options group box.

Click the Update/Add CF Template link in the Report Print Options group box from certain Asset Details and Cost and Depreciation Reports.

Image: ChartField Format Template page

This example illustrates the fields and controls on the ChartField Format Template page. You can find definitions for the fields and controls later on this page.

ChartField Format Template

Report Template

Report ID AMAS2100

CF Template ID [Delete Template](#)

Chartfields					
Field Name	Field Order	Display Length	Label Override	Include in Report	Print subtotals
Operating Unit	<input type="text" value="3"/>	<input type="text" value="8"/>	<input type="text" value="Oper Uni"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Fund Code	<input type="text" value="4"/>	<input type="text" value="5"/>	<input type="text" value="Fund"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Department	<input type="text" value="5"/>	<input type="text" value="10"/>	<input type="text" value="Dept"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Program Code	<input type="text" value="6"/>	<input type="text" value="5"/>	<input type="text" value="Progr"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Class Field	<input type="text" value="7"/>	<input type="text" value="5"/>	<input type="text" value="Class"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Budget Reference	<input type="text" value="8"/>	<input type="text" value="8"/>	<input type="text" value="Bud Ref"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Product	<input type="text" value="9"/>	<input type="text" value="6"/>	<input type="text" value="Produc"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
PC Business Unit	<input type="text" value="10"/>	<input type="text" value="5"/>	<input type="text" value="PC Bu"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Project	<input type="text" value="11"/>	<input type="text" value="15"/>	<input type="text" value="Project"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Activity	<input type="text" value="12"/>	<input type="text" value="15"/>	<input type="text" value="Activity"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Source Type	<input type="text" value="13"/>	<input type="text" value="5"/>	<input type="text" value="Sourc"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Category	<input type="text" value="14"/>	<input type="text" value="5"/>	<input type="text" value="Categ"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Subcategory	<input type="text" value="15"/>	<input type="text" value="5"/>	<input type="text" value="Subca"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>
Asset Category	<input type="text" value="99"/>	<input type="text" value="5"/>	<input type="text" value="Categ"/>	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>

The ChartField Format Template pictured is accessed from the Acquisitions report run control (Asset Management, Financial Reports, Asset Details, Acquisitions, Acquisitions).

Only active PeopleSoft General Ledger ChartFields appear on the page in addition to the PeopleSoft Asset Management ChartField *Asset Category*.

Field Order	Define the order of the fields to print across the page of your report. For example, <i>Department</i> , <i>Project</i> , <i>Product</i> , <i>Asset Category</i> , and so on.
Display Length	Field length defaults automatically appear. Shorten the field lengths as needed.
Label Override	Enter the field label to be used for each field that is included or use the default definitions.
Include in Report	All fields are selected to be included in the report by default. Deselect any fields that you do not want to include.
Print subtotals	The system prints subtotals for all fields by default. Deselect fields for which you do not want subtotal breaks. If a ChartField is not included in the report, corresponding subtotals will not be printed.

Related Links

"Understanding Asset Management Reporting Options (*PeopleSoft FSCM 9.2: Asset Management*)"

Report Fields Format Template Page

Use the Report Fields Format Template page (RPT_FMT_TMPL2_SBP) to update or add new report field formats.

Navigation

Access the run control page for the report to be formatted with user-defined parameters and expand the Report Print Options group box.

Click the Update/Add RF Template link in the Report Print Options group box from certain Asset Details and Cost and Depreciation Reports.

Image: Report Fields Format Template page

This example illustrates the fields and controls on the Report Fields Format Template page. You can find definitions for the fields and controls later on this page.

Report Fields			
Field Label	Include in Report	Override Label	Label Override
Asset ID	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Asset ID
Description	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Description
Cost Type	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Cost Type
Beginning Cost	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Beginning Cost
Additions	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Additions
Transfers	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Transfers
Retirements	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Retirements
Adjustments	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Adjustments
Recategorizes	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Recategorizes
Ending Cost	<input checked="" type="checkbox"/>	<input type="checkbox"/>	Ending Cost

The Report Field Format Template that is pictured was accessed from the Cost Activity report run control (Asset Management, Financial Reports, Cost and Depreciation, Cost Activity, Cost Activity).

Supply an RF Template ID and click the Add Template link. This populates the possible report fields for the particular report.

Include in Report

All fields are selected to be included in the report by default. Deselect any fields that you do not want to include.

Override Label

Select the report fields for which you want to change the field label.

Label Override

Enter the field label to be used for each field that you selected to override.

Related Links

"Understanding Asset Management Reporting Options (*PeopleSoft FSCM 9.2: Asset Management*)"

Setting Up Accounting Entry and Financial Processing for PeopleSoft Asset Management

Setting Up Accounting Entry and Financial Processing for PeopleSoft Asset Management

This topic provides an overview of accounting entry and financial processing and discusses how to:

- Define accounting entries.
 - Define financial processing.
 - Define capitalization threshold processing.
 - Define fair value processing.
 - Define investment property.
 - Enable combination editing.
 - Define document sequencing.
-

Understanding Accounting Entry and Financial Processing

PeopleSoft Asset Management provides the tools to create accounting entries and manage financial reporting for your enterprise. To enable these functions, you must first define the tables used to process accounting entries and financial processes.

You may be required to set up transaction processing with document sequencing. The document sequencing features in PeopleSoft help you to maintain established business practices by meeting these requirements.

Defining Accounting Entries

Use the following components to set up accounting entries:

- Asset Book (BOOK_DEFN1).
- Accounting Entry Template ID (AMAE_TMPL_ID_PNL).

- Accounting Entry Template (DIST_TEMPLATE_DEFN).
- Accounting Templates in Mass (RUN_AMAEMASS).
- Accounting Entry Templates Report (RUN_AMAE1000)
- Transfer Definition (IU_TRF_DEFN_TBL).
- Transaction Codes (TRANSACTION_CODE).
- Transaction Groups (TRANS_PNL_GRP).
- Book Code (BOOK_CODE).
- Acct (accounting) Template Book Code Reset (RUN_AM_BKC_RESET).
- ChartField Mapping Templates (AM_CF_MAPPING).

This topic provides an overview of accounting entry options, lists the pages used to set up accounting entries, and discusses how to:

- Set up transaction codes.
- Set up accounting entry template IDs.
- Create accounting entry templates.
- Create accounting entry templates in mass.
- Set up InterUnit transfer definitions.

Pages Used to Define Accounting Entry for PeopleSoft Asset Management

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Asset Book	BOOK_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Asset Books, Asset Books	Define asset books.
Accounting Entry Template ID	AMAE_TMPL_ID_PNL	Set Up Financials/Supply Chain, Product Related, Asset Management, Accounting, Accounting Entry Template IDs, Accounting Entry Template IDs	Create a template ID with options for depreciation features and distribution methods.

Page Name	Definition Name	Navigation	Usage
Accounting Entry Templates	DIST_TEMPLATE_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Accounting, Accounting Entry Templates, Accounting Entry Templates	Add or modify accounting entry templates. When accessing the Accounting Entry Templates page, you can use a transaction code as a key to determine what accounting entries to create.
Accounting Templates in Mass	RUN_AMAEMASS	Set Up Financials/Supply Chain, Product Related, Asset Management, Accounting, Accounting Templates in Mass, Accounting Templates in Mass	Create one or multiple accounting entry templates for journal templates, cost types, transaction codes, and retirement disposal codes in a single process.
Accounting Entry Templates Report	RUN_AMAE1000	Set Up Financials/Supply Chain, Product Related, Asset Management, Reports, Accounting Entry Templates, Accounting Entry Templates	Run a report showing a list of accounting entry templates.
InterUnit Transfer Definition	IU_TRF_DEFN_TBL	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, InterUnit Transfer Definition, InterUnit Transfer Definition	Set up an InterUnit transfer definition.
Transaction Codes	TRANSACTION_CODE	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Transaction Codes, Transaction Codes	Review or modify the transaction codes.
Transaction Groups	TRANS_GROUP_PNL	Set Up Financials/Supply Chain, Product Related, Asset Management, Accounting, Transaction Groups, Transaction Groups	Set up transaction groups for purposes of allocating depreciation. For example, depreciation and prior period depreciation may be treated the same for allocations, so you can combine them into one transaction group.
Book Code	BOOK_CODE	Set Up Financials/Supply Chain, Common Definitions, Design ChartFields, Define Values, ChartField Values, Book Code	Add book codes in pairs to facilitate multiple GAAP within the same chart of accounts.
Acct Template Book Code Update	RUN_AM_BKC_RESET	Set Up Financials/Supply Chain, Product Related, Asset Management, Accounting, Acct Template Book Code Update, Acct Template Book Code Update	Reset accounting templates book codes in accounting templates.

Page Name	Definition Name	Navigation	Usage
ChartField Mapping Template	AM_CF_MAPPING	Set Up Financials/Supply Chain, Product Related, Asset Management, Accounting, ChartField Mapping Template, ChartField Mapping Template	Create a ChartField map template to map dissimilar charts of accounts when entities have different ChartField structures.

Understanding Accounting Entry Options

PeopleSoft uses tables to support accounting entries for PeopleSoft Asset Management. Some tables are required for accounting entry processing and are noted as such. All others are optional.

Accounting Books

Defining asset books is required for accounting entry processing. Asset books are used to store financial information about assets such as cost history, depreciation rules, and retirement information.

An unlimited number of asset books per business unit can be defined. The number of books that you use depends on your reporting needs. Using multiple books enables you to keep separate cost and depreciation rules for each asset. Typically, organizations use at least two books: corporate and tax, also known as *financial* and *fiscal*. Your organization may need additional books if it does business in more than one state or country or uses any of the United States-recognized special tax treatments of accelerated current earnings (ACE) and alternative minimum tax (AMT).

Note: The depreciation criteria for each book are specified when you add assets or create asset profiles.

Accounting Entry Templates

The Accounting Entry template is the central table used for creating accounting entries to general ledger journals. Each is defined by an accounting entry template ID. When you add an accounting entry template, PeopleSoft Asset Management populates it with standard accounting entry types, based on the asset category, cost type, and transaction type that you specify. It also identifies each entry as either a debit or credit.

To begin, create accounting entry template IDs and if applicable in your business, mark the cost types for impairment and revaluation. For the SetID, create or select an existing accounting entry template to apply depreciation features and distribution methods. These features control what distribution types need to be set up in the accounting entry template.

PeopleSoft Asset Management enables you to create one or multiple accounting entry templates in a single operation. You may generate accounting entry templates for an asset category for all transaction types. You can generate templates for cost type, transaction code, and retirement disposal code.

Once you have defined the accounting entry template IDs, run the Create Accounting Templates in Mass Application Engine process (AMAEMASS) that generates accounting entry templates for all transaction types and user-defined cost type, transaction code, and disposal code.

Multiple GAAP and Book Codes

PeopleSoft delivers the ability to book accounting transactions according to different and often conflicting accounting principles for one Business Unit in one ledger and to maintain these entries in compliance

with the rules of government and regulatory organizations. You can add book codes for PeopleSoft Asset Management to facilitate accounting entry processing.

Generally accepted accounting principles (GAAP) as determined in one country or jurisdiction often vary from country to country or by self-governing accounting bodies and jurisdictions. Consequently, organizations record and report their operations according to local accounting requirements as well as by rules applicable to parent corporations that are often under the rules of another national jurisdiction. PeopleSoft has provided the ability to maintain separate ledgers and ledger groups for different accounting principles, record transactions under varying statutory rules using Alternate Account and using MultiBook in PeopleSoft General Ledger and its subsystems for its automatic synchronization capabilities. A sometimes much favored method, especially within financial organizations, is defining book codes. This method enables you to simultaneously generate in one business unit and ledger all the relevant accounting entries for a transaction that addresses different local and corporate accounting rules.

You can use book codes to simultaneously generate sets of entries to record related transactions according to multiple GAAP for the same business unit in the same ledger. For example, where local and corporate accounting principles are not compatible, you define a local (L) and a corporate (C) book code. For those situations where requirements are alike, you define a code for both (B). You can attach these book codes to accounts as attributes. This results in separate permutations of accounts and book codes in which you simultaneously record related transactions under local, corporate, or both rules. You can choose to associate a single book code with one account value. Using this method, a unique account value must be created for each book code.

See "Understanding Multiple GAAPs and Prior Period Adjustments (*PeopleSoft FSCM 9.2: Global Options and Reports*)".

Prerequisites

Before you can define accounting entry processing, you must first complete the following task:

- Define overall installation options to enable Book Code functionality. Use the Installation Options Overall (INSTALLATION_FS1) page.
- Define ChartField accounts.
- Define journals, ledgers and ledger groups.

Transaction Codes Page

Use the Transaction Codes page (TRANSACTION_CODE) to review or modify the transaction codes.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Transaction Codes, Transaction Codes

Image: Transaction Codes page

This example illustrates the fields and controls on the Transaction Codes page. You can find definitions for the fields and controls later on this page.

Transaction Codes		Personalize Find [?] []		First	1-12 of 12	Last
	*Transaction Code	Description	Short Description			
1	1	Acquisition-Education Division	Education	+	-	
2	A	Abandoned	Abandoned	+	-	
3	C	Cannibalized	Cannibal	+	-	
4	I	Inventory	Inventory	+	-	
5	IP	Investment Property	Inv Prop	+	-	
6	N	Donated	Donated	+	-	
7	O	ARO Settlement	ARO Settle	+	-	
8	R	Scrap	Scrap	+	-	
9	RV	Revaluation	Reval	+	-	
10	S	Sale	Sale	+	-	
11	T	Trade-in	Trade-in	+	-	
12	Y	Casualty	Casualty	+	-	

Transaction Code

Enter a transaction code that identifies special asset transactions and that are used in combination with actions to create accounting entries. You can modify these codes by changing the description and short description. The transaction code associated with revaluation displays revaluation related distribution types for additions.

When you define accounting entry options for a book, you can choose to distribute by disposal code. If you choose this option, the disposal code appears by default as the transaction code. In this case, you must use the transaction codes from the delivered TableSet defined for the tubbiest that you are using. You must also define corresponding accounting entry templates.

Note: The standard transactions are predefined and delivered with PeopleSoft Asset Management. To modify the transaction types, use the Asset Management (INSTALLATION_AM) page of the Installation Options (INSTALLATION) component.

See "Installation Options - Asset Management Page (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

Accounting Entry Template IDs Page

Use the Accounting Entry Template IDs page (AMAE_TMPL_ID_PNL) to create a template ID with options for depreciation features and distribution methods.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Accounting, Accounting Entry Template IDs, Accounting Entry Template IDs

Image: Accounting Entry Template IDs page

This example illustrates the fields and controls on the Accounting Entry Template IDs page. You can find definitions for the fields and controls later on this page.

(FRA) Derogatory Depreciation

Select to accumulate derogatory depreciation. Used in France, derogatory depreciation represents the difference between two methods of depreciation (usually straight-line versus declining balance) applied to the same asset, where one method best reflects the economic depreciation and the other is used for tax reporting purposes.

(USA) Like Kind Exchange

Select to accumulate like kind exchange in support of the US 1031 Like-Kind Exchange guidelines issued by the Internal Revenue Service (IRS).

Note: Selecting this check box results in unrecognized gain and loss.

Revaluation

Select to accumulate differences derived from revaluation of tangible fixed assets and financial assets. This option not available if you have not selected the revaluation option on the Installation Options — Asset Management page.

Book Code

Select this check box to apply book code to this accounting entry template ID. If it is not applicable, all generated entries will be created with no Book Code and all entries will post to General Ledger. If it is applicable, the book code functionality will be applied either for every book or none of them in the

same ledger group by default. This field appears only if the Book Code feature is enabled at the system level within overall Installation Options.

**Cap Threshold Processing
(capitalization threshold processing)**

Select to enable capitalization threshold processing at the accounting entry template ID level. This option appears only when the Capitalization Threshold feature is enabled at the system level within Installation Options.

See Defining Capitalization Threshold Processing

Create Gain/Loss Lines

Select this distribution method to distribute the accounting entries created by the template to gain and loss totals. There are two general methods of registering a fixed asset's sales. Create Gain/Loss Lines is used to reflect in only one account the gain or loss that the sale transaction represents for the company.

Create Net Book Value lines

Select this distribution method to distribute the accounting entries created by the template to net book value totals. There are two general methods of registering a fixed asset's sales. Create Net Book Value lines is used to reflect the proceeds of the sale in one account and the cost of sold asset in the other account. The PeopleSoft system provides the flexibility to generate entries for the wanted method.

Note: When setting up a new template or changing a template ID on a template that previously used either Gain/Loss or Net Book Value distribution, you may see a warning that the previous templates will be deleted. You have the option to go back and update the template instead.

Related Links

"Understanding PeopleSoft Asset Management in Global Settings (*PeopleSoft FSCM 9.2: Asset Management*)"

Accounting Entry Templates Page

Use the Accounting Entry Templates page (DIST_TEMPLATE_DEFN) to add or modify accounting entry templates.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Accounting, Accounting Entry Templates, Accounting Entry Templates

Image: Accounting Entry Templates page

This example illustrates the fields and controls on the Accounting Entry Templates page. You can find definitions for the fields and controls later on this page.

Accounting Entry Templates

Accounting Entry Template

SetID SHARE

Asset Category AUTO Automobile

Cost Type A Allowance for ADV Depr

Transaction Type ADD Asset Addition

Transaction Code I Inventory

Account Entry Template ID AUSTRALIA Acctg Template ID Australia

*Journal Template Asset Additions

Budget Journal Template ID Asset Additions

Accounting Entries

Accounting Entry Type	*Account	Alternate Account	DR/CR
Accumulated Depr	<input type="text" value="165000"/>	<input type="text"/>	Credit
Contra Asset	<input type="text" value="674000"/>	<input type="text"/>	Credit
Depr Expense	<input type="text" value="681500"/>	<input type="text"/>	Debit
Fixed Asset	<input type="text" value="155000"/>	<input type="text"/>	Debit
Recognized Loss	<input type="text" value="682100"/>	<input type="text"/>	Credit
Trade In	<input type="text" value="120000"/>	<input type="text"/>	Credit
Unrecog Gain/Loss	<input type="text" value="110000"/>	<input type="text"/>	Debit

Set up an accounting entry template for each possible combination of:

- Asset category.
- Cost type.
- Transaction type.
- Transaction code.
- Accounting entry template ID.

Note: If you enter an asset into your system by using a combination of these values for which no accounting entry template exists, your accounting entry process fails when you next attempt to run it.

For each accounting entry type, select:

Journal Template For recording actual transactions.

Budget Journal Template For recording budget transactions.

Accounting Entries

Select the appropriate accounts and alternative accounts to be associated with each accounting entry type.

If Book Code functionality is set up at Accounting Entry Template IDs level, the Accounting Entry Templates page displays the Book Code related to that account.



Click the refresh button to update the display after you enter changes.

Accounting Entry Types

Accounting entry types are set by the system. Each asset event has an associated set of accounting entry types.

For each possible combination of category, cost type, and transaction code, you must set up an accounting entry template for each of the following transaction types:

- *ADD*: Additions.
- *ADJ*: Adjustments.
- *TRF*: Transfers.
- *RCT*: Recategorizations.
- *DPR*: Depreciation expenses.
- *PDP*: Prior period depreciation.

Note: The *DPR* and *PDP* transaction types are used only on an accounting entry template with a blank transaction code.

- *RET*: Retirements (also used for processing reinstatements).
- *LPY*: Lease payments.
- *INF*: Inflation adjustment.

Book Code

Specify a book code for each account value.

The Allow Book Code Override option that is set on the Account (ACCOUNT) page determines whether this book code can be overridden on the transaction line. The Effective Date and Status fields on the Account page must match the settings for the account values to which the book code is attached. Assets take the most recent and active date to populate its templates. To avoid any situation where Book Code might generate unbalanced entries in General Ledger, a warning message is generated when the template is saved when there are *paired* distribution types with different Book Codes. Paired distribution types are those distribution types that play against other in order to balance the entry.

Accounting Templates in Mass Page

Use the Accounting Templates in Mass page (RUN_AMAEMASS) to create one or multiple accounting entry templates for journal templates, cost types, transaction codes, and retirement disposal codes in a single process.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Accounting, Accounting Templates in Mass, Accounting Templates in Mass

Image: Accounting Templates in Mass page (1 of 3)

This example illustrates the fields and controls on the Accounting Templates in Mass page (1 of 3). You can find definitions for the fields and controls later on this page.

Accounting Templates in Mass

Run Control ID EIP Report Manager
Process Monitor
Run

Request Find | View All First 1 of 1 Last

*Request ID

*SetID

*Category

Process Frequency

*Account Entry Template ID

Delete All Cost Types
Delete All Trans Codes
Delete All Disposal Codes

Accounting Entries	Distribution Type	*Account	Alternate Account
Investment Property		<input type="text" value="152000"/>	<input type="text"/>
Inv Property Gain		<input type="text" value="673100"/>	<input type="text"/>
Inv Property Loss		<input type="text" value="675100"/>	<input type="text"/>
Accumulated Depr		<input type="text" value="162000"/>	<input type="text"/>
Contra Asset		<input type="text" value="159002"/>	<input type="text"/>
Trade In		<input type="text" value="120000"/>	<input type="text"/>
Proceeds		<input type="text" value="830000"/>	<input type="text"/>
Removal Contra		<input type="text" value="899994"/>	<input type="text"/>
Proceeds to Billing		<input type="text" value="899993"/>	<input type="text"/>
Depr Expense		<input type="text" value="681750"/>	<input type="text"/>
Unrecog Gain/Loss		<input type="text" value="110000"/>	<input type="text"/>
Unrealized Gain		<input type="text" value="110000"/>	<input type="text"/>
Unrealized Loss		<input type="text" value="110000"/>	<input type="text"/>
Recognized Gain		<input type="text" value="675100"/>	<input type="text"/>
Recognized Loss		<input type="text" value="675100"/>	<input type="text"/>

Image: Accounting Templates in Mass page (2 of 3)

This example illustrates the fields and controls on the Accounting Templates in Mass page (2 of 3). You can find definitions for the fields and controls later on this page.

Journal Template ID		
Journal Template Id		
Transaction Type	*Journal Template	Budget Journal Template ID
Accretion Expense	ADD	ADD
Asset Addition	ADJ&TRANS	ADJ&TRANS
Asset Cost Adjustment	PC_ADJUST	PC_ADJUST
Depreciation	DEPR	DEPR
Inflation Adjustment	RAD	RAD
Prior Period Depreciation	DEPR	DEPR
Asset Recategorization	RECAT	RECAT
Asset Retirement	RET	RET
Asset Transfer	ADJ&TRANS	ADJ&TRANS

Cost Type		
Cost Type		
Cost Type	Short Description	
A	Allowance	+ -
C	Cost	+ -
G	Grant	+ -
I	IMP Loss	+ -
M	Margin	+ -
O	ARO	+ -
P	Scrap on A	+ -
R	Reval	+ -
S	Sales of A	+ -
V	Reserve	+ -
W	Depr.W-Off	+ -
X	Reval Rev	+ -
Y	Imp Rev	+ -
		+ -

Image: Accounting Templates in Mass page (3 of 3)

This example illustrates the fields and controls on the Accounting Templates in Mass page (3 of 3). You can find definitions for the fields and controls later on this page.

Transaction Codes			
Transaction Codes			
Trans Code	Short Description		
1	Education	+	-
A	Abandoned	+	-
C	Cannibal	+	-
I	Inventory	+	-
IP	Inv Prop	+	-
N	Donated	+	-
O	ARO Settle	+	-
R	Scrap	+	-
RV	Reval	+	-
S	Sale	+	-
T	Trade-in	+	-
Y	Casualty	+	-
		+	-

Retirement Disposal Code			
Retirement Disposal Codes			
Trans Code	Short Description		
1	Acquisitio	+	-
A	Abandoned	+	-
C	Cannibaliz	+	-
I	Inventory	+	-
IP	Investment	+	-
N	Donated	+	-
O	ARO Settle	+	-
R	Scrap	+	-
RV	Revaluatio	+	-
S	Sale	+	-
T	Trade-in	+	-
Y	Casualty	+	-
		+	-

When you begin the process, the page displays your request ID and default process frequency. Select the SetID, account entry template ID, and category. Three actions can be carried out:

Delete All Cost Types

Select to erase all cost types displayed in the Cost Type group box.

Delete All Trans Codes (delete all transaction codes)

Select to erase all transaction codes displayed in the Transaction Codes group box.

Delete All Disposal Codes

Select to erase all disposal codes displayed in the Retirement Disposal Code group box.

Distribution Options

The page displays a distribution type list and corresponding account and alternate account specific to the template ID or category selected. The list is refreshed when these values change.

If Book Code functionality is set up at Accounting Entry Template ID level, the book code related to the account displays. The Allow Book Code Override option set on the Account page determines whether the book code can be overridden for each distribution type. This process populates the book codes using the criteria defined for the Accounting Entry Template.

If the book code column does not display, it is not selected at Accounting Entry Template ID level. The template uses the book code based on the accounts effective date set in the Account definition page.

SetID Options

The page includes expandable subpages of options determined by SetID.

Journal Template ID

(AM_JRNL_TMPL_SBP, RUN_AMAEMASS_02)

Select journal and budget journal templates for each type of transaction (add, adjust, and so forth).

Cost Type

(AM_COST_TYPE_SBP, RUN_AMAEMASS_03)

Select cost types for which templates should be generated (cost, margin, revaluation, and so forth). If cost types are not used, leave this field blank.

Transaction Codes

(AM_TRANS_CODE_SBP, RUN_AMAEMASS_04)

Select transaction codes for which templates should be generated (abandoned, inventory, donated, and so forth).

Retirement Disposal Code

(AM_RETDISP_CODE_SBP, RUN_AMAEMASS_05)

Select retirement code for which templates should be generated (abandoned, inventory, donated, and so forth).

Related Links

"Understanding Asset Information Flow (*PeopleSoft FSCM 9.2: Asset Management*)"

InterUnit Transfer Definition Page

Use the InterUnit Transfer Definition page (IU_TRF_DEFN_TBL) to set up an InterUnit transfer definition.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, InterUnit Transfer Definition, InterUnit Transfer Definition

Image: InterUnit Transfer Definition page

This example illustrates the fields and controls on the InterUnit Transfer Definition page. You can find definitions for the fields and controls later on this page.

To begin, from the search dialog page, select the books used by the To Business Unit business unit.

From Book

Enter the book whose information you want to enter into the To Book. Then select the action that you want to use: *Transfer* or *Add* book. Usually you use the transfer action.

InterUnit transfer definitions act as templates to simplify performing InterUnit transfers.

InterUnit transfer definitions tell the system which books exist for the *transfer from* and *transfer to* business units, and what type of transactions the InterUnit transfer should generate for each book. If you are planning to perform many InterUnit transfers, it helps to first define all the possible InterUnit transfers.

For example, if you have three business units, US001, US002, and US003, and you expect to perform all possible InterUnit transfers, you would set up these six InterUnit transfer definitions:

<i>Transfer From</i>	<i>Transfer To</i>
US001	US002
US001	US003
US002	US001
US002	US003
US003	US001
US003	US002

When transferring from a business unit with two books to a business unit with three books, enter information into the extra To Book by using either the Add Book action or the Transfer Book action.

For example:

From Book	To Book	Action
Corporate	Local	Transfer Book
Federal	Reporting	Transfer Book
Corporate	Other	Add Book

The transactions generated to pass book information for InterUnit transfers differ depending on how many To Book entries a From Book is passing information to, and whether it is passing the information by using a transfer action or an add book action.

Note: Assets that are transferred to new business units by using the add action will have a cost row of zero on the new business unit until you run the Depreciation Calculation process (AM_DEPR_CALC). Running this process updates the asset's cost row with its net book value from the From Book. When you use an asset profile, the book information appears by default from the profile.

Using a From Book Once

When a From Book is used once only, an add action generates a retirement for the From Book and an add to the To Book. A transfer action generates a transfer out for the From Book and a transfer in for the To Book.

The asset that is retired receives an asset status of Disposed.

Assets that are transferred between books by using the transfer action receive a status of Transferred:

From Book	From Trans	To Book	To Trans	Action
CORPORATE	Transfer Out	CORPORATE	Transfer In	Transfer Book
FEDERAL	Transfer Out	FEDERAL	Transfer In	Transfer Book
From Book	From Trans	To Book	To Trans	Action
CORPORATE	Transfer Out	CORPORATE	Transfer In	Transfer Book
FEDERAL	Retire	FEDERAL	Add	Add Book
From Book	From Trans	To Book	To Trans	Action
CORPORATE	Retire	CORPORATE	Add	Add Book
FEDERAL	Retire	FEDERAL	Add	Add Book

Using a From Book for Two or More Transfers

When a From Book is used for two or more transfer book actions, only one transfer out transaction is generated. Because this takes care of the cost on the From Book, no additional transfer outs are generated for that book.

Assets that are transferred between books by using the transfer book action receive a status of Transferred:

From Book	From Trans	To Book	To Trans	Action
CORPORATE	Transfer Out	CORPORATE	Transfer In	Transfer Book
CORPORATE		LOCAL	Transfer In	Transfer Book

Using a From Book for Both Transfer and Add

When a From Book is used for both a transfer and an add action, a transfer out is generated for the Transfer Book. Because this takes care of the cost on the From Book, the add action does not generate a retirement for that book.

Assets that are transferred between books by using the transfer book action receive a status of Transferred:

From Book	From Trans	To Book	To Trans	Action
CORPORATE	Transfer Out	CORPORATE	Transfer In	Transfer Book
CORPORATE		LOCAL	Add	Add Book

Using a From Book for Two or More Adds

When a From Book is used for two or more add actions, a retirement is generated for the first add action. Because this takes care of the cost on the From Book, no further retirements are generated for it.

The asset that was retired receives a status of Disposed:

From Book	From Trans	To Book	To Trans	Action
CORPORATE	Retire	CORPORATE	Add	Add Book
CORPORATE		LOCAL	Add	Add Book

Note: When you transfer from a business unit with three books to a business unit with two books, the cost information on the extra From Book is automatically retired. You do not need to enter an action.

See "Understanding Adjusting, Transferring, and Evaluating Assets (*PeopleSoft FSCM 9.2: Asset Management*)".

Retiring a Book

Assets that are retired receive a status of Disposed:

From Book	From Trans	To Book	To Trans	Action
CORPORATE	Transfer Out	CORPORATE	Transfer In	Transfer Book
LOCAL	Transfer Out	LOCAL	Transfer In	Transfer Book
FEDERAL	Retire			

See "Understanding Asset Retirement (*PeopleSoft FSCM 9.2: Asset Management*)".

Defining Financial Processing for PeopleSoft Asset Management

Use the Asset Categories (CATEGORY_DEFN) component and the Capitalization Limits (DEPR_CAP_LIMIT) component to define financial processing in PeopleSoft Asset Management.

This topic provides an overview of financial processing, lists the pages to define financial processing and describes how to:

- Define asset categories.
- Set up capitalization limits.
- Set up capitalization threshold processing.
- Set up fair value processing.

Pages Used to Define Financial Processing

Page Name	Definition Name	Navigation	Usage
Categories	CATEGORY_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Categories, Categories	Establish asset categories, which classify assets by type for accounting entry purposes. Typically, these categories reflect how assets are reported on balance sheets. Examples of commonly used asset categories are Furniture and Fixtures, Machinery and Equipment Office Equipment, Leasehold Improvements, and so forth.
Inflation Information	CATEGORY_SEC	Click the Inflation Information link from the Category page.	Establish an inflation adjustment factor by selecting the market index and rate to apply.

Page Name	Definition Name	Navigation	Usage
Asset Categories Report	RUN_AMAS1100	Set Up Financials/Supply Chain, Product Related, Asset Management, Reports, Asset Categories, Asset Categories	Run a report on asset categories.
Cost Types	COST_TYPE_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Cost Types, Cost Types	Define cost types.
Financing Codes	FINANCING_CD	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Financing Codes	Define financing codes to help you analyze your debit and credit relationships for capital-intensive and government projects. For example, you could set up codes to identify bonds, such as IRBs, IDBs, and TEBs.
Indexes	AM_INDEX_TBL	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Indexes	Set up an index, which is used to remeasure assets according to set percentages. Gain and loss on retirement is then calculated by using the resulting net book value. Indexes are usually maintained by regulatory agencies, but you can set up your own as well. You can set up rates to associate with indexes on the Defining Market Rates page.
C.A.P. Types (capital acquisition plan types)	CAP_TYPE	Set Up Financials/Supply Chain, Product Related, Asset Management, Profiles, Capital Acquisition Plan Types	Set up C.A.P. types. If you are using Asset Budgeting, you set up codes to be used with the C.A.P. function. You can also use C.A.P. type codes to track assets acquired as part of a C.A.P.
Capitalization Limit	DEPR_CAP_LIMIT	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Capitalization Limit	Set up capitalization limit codes by business unit by book, as necessary, especially Germany.
Capitalization Thresholds	CAP_THR_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Capitalization Thresholds, Capitalization Thresholds	Establish capitalization thresholds by asset profile to be used in automatic classification of capital asset, noncapital asset or expense asset.

Page Name	Definition Name	Navigation	Usage
Cap Threshold Validation	AM_CAPVAL_RQST	Asset Management, Financials, Capitalization Thresholds, Capitalization Thresholds	Run the process to validate whether an asset still meets conditions to remain in the capitalization status that it was originally catalogued upon asset addition based on the capitalization threshold process.
Clearing Reconciliation	AM_CLEREC_RQST	Asset Management, Accounting Entries, Clearing Reconciliation	Run the process to reconcile the clearing account that is created by trackable assets from feeder systems against the expense account.
Review Expense Entries	ASSET_NF_DIST	Asset Management, Accounting Entries, Review Expense Entries	Run a report to show the capitalization status of assets based upon criteria selection.
Capitalization Summary Report	AM_CAPSUM_RQST	Asset Management, Financial Reports, Capitalization Summary Report	Run a report to show the capitalization status of assets based upon criteria selection.

Understanding Financial Processing in PeopleSoft Asset Management

PeopleSoft Asset Management enables you to apply various attributes to assets for financial reporting purposes, such as categories, cost types, financing codes, and indexes. The purpose of defining these asset attributes is to help refine asset information into meaningful information blocks.

The combination of asset category and transaction code determines into which accounts an asset transaction is entered. Asset category is required.

To group assets by class for reporting or informational purposes only, use the asset class field.

Cost types represent different cost components of an asset, such as materials, labor, and overhead. For example, you can differentiate between the cost of building an asset and its market value by allocating the cost of production to one cost type and the margin of profit to another cost type. Cost type, in combination with asset category and transaction code, determines into which accounts the costs are entered in the general ledger.

Use indexes to remeasure assets according to set percentages. An index may consist of several subindexes, each of which has a separate index amount. You can set up a subindex for each asset category, with amounts that correspond to the inflation or valuation percentages for that year.

You also use indexes and subindexes to calculate replacement costs for assets. Tying an index, such as the consumer price index (CPI), to an asset profile enables replacement cost to be updated in adjustment, partial InterUnit transfer, partial retirement, and partial reinstatement transactions. Revaluation indexes are usually dictated by regulatory agencies, but you can also set up your own.

In compliance with Financial Accounting Standards (FAS) 157, which establishes U. S. guidelines for measuring the fair values of assets and liabilities, PeopleSoft Asset Management provides a framework by which to designate the appropriate valuation method for proper fair value valuation processing. Asset Management also supports fair value processing for international organizations.

PeopleSoft Asset Management validates capitalization limits when you add assets. At the business unit or book level, indicate whether validation should occur against a specific limit or against a table where you have stored step limit amounts and specified various messages for assets whose costs fall below these steps. You can also specify incremental valuation thresholds that identify the asset as a low value asset and how it should be treated during processing. The capitalization limit table accommodates the processing requirements of various countries. In some countries, a low value asset must be fully depreciated in the year of acquisition; in others, a low value asset may be added but must be taken as an expense.

PeopleSoft Asset Management can also determine capitalization status of an asset based on its cost according to capitalization thresholds that you define. When adding new assets, either online or batch, the system automatically classifies them according to their cost into capital assets, noncapital assets or expense assets. You create a Capitalization Threshold for each profile of asset that you want to evaluate and associate it with that asset profile. Processes are available to validate capitalization status and deal with adjustments to the original cost, reconcile any potential clearing account with feeder systems, and access reports and audit trails to facilitate control of these transactions.

See the topic “Capitalization Threshold” in "Understanding Adding and Maintaining Assets (*PeopleSoft FSCM 9.2: Asset Management*)"

Categories Page

Use the Categories page (CATEGORY_DEFN) to establish asset categories, which classify assets by type for accounting entry purposes.

Typically, these categories reflect how assets are reported on balance sheets. Examples of commonly used asset categories are Furniture and Fixtures, Machinery and Equipment Office Equipment, Leasehold Improvements, and so forth.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Categories

Image: Categories page

This example illustrates the fields and controls on the Categories page. You can find definitions for the fields and controls later on this page.

The screenshot displays the 'Categories' page in PeopleSoft. At the top, the title 'Categories' is shown. Below it, the page is divided into several sections. The 'SetID' is 'SHARE' and the 'Asset Category' is 'AUTO'. The 'Category Definition' section contains the following fields and controls:

- *Effective Date: 01/01/1900
- *Status: Active (dropdown menu)
- *Description: Automobile
- Inflation Information: (link)

Below the 'Category Definition' section, there are two main sections:

- Depreciable Status:** Contains two radio buttons: 'Depreciable' (selected) and 'Non Depreciable'.
- Options:** Contains four checkboxes: 'Intangible', 'Leased Assets', 'Investment Property', and 'Property Interest'.

Complete the appropriate fields for each asset category. Identify the depreciable status as Depreciable or Non Depreciable. You can optionally associate inflation processing information with the category.

See [Setting Up Asset Profiles](#).

Options

These options drive the accounting entries to display in the accounting entry template. When possible, assign these options at the asset category level to alleviate this identification at the individual asset level. Identification at the category or profile level is also necessary for handling batch transactions where there is no use intervention.

Intangible

Select if the asset category applies to intangible assets.

Leased Assets

Select if the asset category applies to leased assets.

Investment Property

Select if the asset category applies to assets that are considered investment property as defined by International Accounting Standards (IAS) 40. This selection can be used in conjunction with the Leased Assets check box if the category applies to leased assets that are also investment property. However, you cannot select the Intangible check box and the Investment Property check box in combination. A warning message appears in the event that you select this invalid combination.

See [Defining Investment Property](#).

Property Interest

Select if the asset category applies to an operating lease that meets the conditions for investment property as defined by IAS 40. Operating leases that fall under this category are not treated as operating leases according to Financial Accounting Standards (FAS) 13, which are normally expensed, but rather as capital leases for accounting purposes (capitalized and amortized over the lease term). The Leased Asset check box must also be selected when selecting this option. A message alert appears upon saving the page if the Property Interest check box is selected without the selection of the Leased Assets check box.

Cost Types Page

Use the Cost Types page (COST_TYPE_DEFN) to define cost types.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Cost Types, Cost Types

Image: Cost Types page

This example illustrates the fields and controls on the Cost Types page. You can find definitions for the fields and controls later on this page.

Impairment Process

Select to use this cost type for impairment. Selecting this check box displays impairment related accounts at the accounting entry template level. This field is not displayed if impairment options are not selected on the Installation Options - Asset Management page.

Note: This option cannot be selected with the Revaluation Process option for a single cost type.

Revaluation Process

Select to use this cost type for revaluation. Selecting this check box displays revaluation related accounts at the accounting entry template level. This field is not displayed if revaluation options are not selected on the Installation Options - Asset Management page.

Note: This option cannot be selected with the Impairment Process option for a single cost type.

Asset Retirement Obligations

Select to use this cost type for ARO (asset retirement obligation) processing. Selecting this check box displays ARO-related accounts at the accounting entry template level. This field is not displayed if ARO options are not selected on the Installation Options - Asset Management page.

Note: This option cannot be selected with the Impairment Process option or the Revaluation Process option for a single cost type.

Note: When selecting a cost type for processing, you should update the accounting entry templates because new accounting entries need to be set up for these transactions.

Capitalization Limits Page

Use the Capitalization Limits page (DEPR_CAP_LIMIT) to set up capitalization limit codes by business unit by book, as necessary, especially Germany.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Capitalization Limit

Image: Capitalization Limits page

This example illustrates the fields and controls on the Capitalization Limits page. You can find definitions for the fields and controls later on this page.

Capitalization Limits			
SetID		SHARE	
Cost Limit Code	GERMANY	*Currency Code	EUR euro
Description	Germany Depreciation Limits		
Limits Personalize Find First 1-2 of 2 Last			
Amount	Low Value Switch	Message Severity	
1 100.00	<input type="checkbox"/>	Error	
2 800.00	<input checked="" type="checkbox"/>	Warning	

Create a cost limit code, complete the applicable fields, and select the Low Value Switch check box to identify which limit amount triggers low value asset reporting. This is used only in certain countries.

For example, you might set up capitalization limits for Germany. Using the Cap Limit table, you can set up your system so that assets with a cost less than 800.00 EUR could be added, but the system would generate a warning that the cost was below the capitalization limit; likewise, assets with a cost less than 100.00 EUR could *not* be added and would generate an error message.

Related Links

"Capitalization Limits Page (*PeopleSoft FSCM 9.2: Asset Management*)"

Capitalization Thresholds Page

PeopleSoft Asset Management can determine capitalization status of an asset based on its cost or quantity according to limits that you define. This can be accomplished by enabling the optional Capitalization

Threshold feature. Once you enable this feature and complete the required setup, the system automatically classifies assets using the defined thresholds when adding new assets, either online or in batch: Assets are classified within one of the following categories:

- Capital Assets - The system generates an asset ID and stores physical and financial information. Financial information is stored in the cost table (COST). The system also stores acquisition details. Therefore, these assets are trackable from both a physical and financial standpoint. This term is interchangeable with Financial Assets.
- Noncapital Assets - The system generates an asset ID and stores only physical information. The cost information is stored in the noncapitalized cost table, (COST_NON_CAP). The system also stores acquisition details. Therefore, these assets are trackable from a physical standpoint only. This term is synonymous with Trackable Assets or Nonfinancial Assets.
- Expense Assets - The system does not generate an asset ID. If an asset is entered online that does not meet the capitalization threshold, an error message appears saying that the asset has been catalogued as an expense due to its cost amount and could not be considered as an asset. If the asset is entered in batch, the system stores a message in an audit table that explains why that interface line was not processed. Because of their low cost, these assets are considered an expense when acquired and there is no interest in tracking them within the Asset Repository.

To begin using the Capitalization Threshold feature, complete the following setup steps:

1. Enable the Cap Threshold Processing option at the system level within Installation Options - Asset Management.

See "Installation Options - Asset Management Page (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

2. Enable the Capitalization Threshold option at the business unit level.

See Understanding Asset Management Business and Cash Generating Units.

3. Define Capitalization Thresholds and associate them to the appropriate asset profiles.

Use the Capitalization Thresholds page (CAP_THR_DEFN) to establish capitalization thresholds by asset profile to be used in automatic classification of capital asset, noncapital asset or expense asset.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Capitalization Thresholds, Capitalization Thresholds

Image: Capitalization Thresholds page

This example illustrates the fields and controls on the Capitalization Thresholds page. You can find definitions for the fields and controls later on this page.

Capitalization Thresholds

SetID SHARE

Threshold ID CT_001

*Basis Amount

*Currency Code USD

*Description Capitalization on Amount

Detail Find | View All First 1 of 1 Last

Effective Date 01/01/1900

Thresholds			
	Active	Action	Amount
1	<input checked="" type="checkbox"/>	Expense	500.00
2	<input checked="" type="checkbox"/>	Physical	5,000.00

Threshold ID

Supply a meaningful threshold ID when creating capitalization thresholds to assign them to asset profiles or assets.

Basis

Select the basis to be used for calculating the appropriate capitalization action to take. Select from the following options:

- *Amount*: The capitalization threshold is based on the total cost of an asset (cost x quantity).
- *Quantity*: The capitalization threshold is based on the unit costs per asset.

Currency Code

Enter the currency code of the amounts reflected in the Amount fields.

Effective Date

Enter the date when the threshold becomes applicable.

Active

Activate each threshold bracket. When deselected, the amount becomes unavailable.

Action

Select to activate and set thresholds for the following brackets:

- **Physical:** If this action is active and an asset falls within the threshold for this bracket, the system creates the asset ID but does not capitalize it. Any asset added that has an amount above this bracket is capitalized if this bracket is active.
- **Expense:** If this action is active and falls within the threshold for this bracket, the asset is excluded from asset generation. If however, the Physical bracket is not active and an asset amount is above the Expense limit, the asset is capitalized.

Amount

Enter the ceiling amount for each bracket. Amounts that are less than or equal to the amount entered are included in that bracket.


Capitalization Threshold Validation Page

The Capitalization Threshold Validation process validates whether assets still belong to the capitalization brackets to which they were initially catalogued after adjustments are made to the original cost. If an asset is in the same bracket as originally classified, then this process takes no further action; however, if it is not, the asset is moved to its respective capitalization bracket.

The following graphic represents the process flow for the capitalization threshold validation process:

Image: Capitalization Validation process flow

Capitalization Threshold validation process flow:



Use the Capitalization Threshold Validation page (AM_CAPVAL_RQST) to run the process to validate whether an asset still meets conditions to remain in the capitalization status that it was originally catalogued upon asset addition based on the capitalization threshold process.

Navigation

Asset Management, Asset Transactions, Financial Transactions, Cap Threshold Validation

Image: Capitalization Threshold Validation page

This example illustrates the fields and controls on the Capitalization Threshold Validation page. You can find definitions for the fields and controls later on this page.

Supply the selection criteria for assets to be evaluated for capitalization threshold validation.

Chartfield Search Criteria link

Access the Chartfield Search Criteria page to supply ChartField filter information for those assets that have particular ChartFields active.

Trans Code (transaction code)

Select this criteria, which is useful for assets that are converted from trackable to capitalized. If you want to identify them or perform a different accounting entry, you can define and utilize a transaction code for that purpose.

Validation Basis

Select the criteria to use in order to evaluate the total cost of the asset against the threshold. The following options are available:

- *Capitalized Cost* : The system sums only the amounts stored on the cost table.
- *Total Cost*: The system sums up the amounts stored in both the cost and non capital cost tables.

Clearing Reconciliation Page

When an asset is deemed trackable by the capitalization threshold process, the asset ID is generated but in fact no accounting activities take place. Additionally, when assets are added through feeder sources, it is likely to debit the Fixed Account and credit a Clearing account that was previously debited at the source

accounting. The Clearing Reconciliation process provides a way to balance out (credit) the clearing account that was previously debited at the source product accounting and debit the expense account. This is not applicable to the trackable assets that are entered directly into Asset Management with no clearing account at all. In this instance, the expense account is most likely debited when the asset is added.

This process checks the noncapital cost lines, determines the expense and clearing accounts from the accounting entry templates and inserts rows into the staging table (DIST_LN) to be loaded as journal entries into general ledger for posting.

Use the Clearing Reconciliation page (AM_CLEREC_RQST) to run the process to reconcile the clearing account that is created by trackable assets from feeder systems against the expense account.

Navigation

Asset Management, Accounting Entries, Clearing Reconciliation

Image: Clearing Reconciliation page

This example illustrates the fields and controls on the Clearing Reconciliation page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Clearing Reconciliation' page. At the top, there are navigation links: 'Run Control ID', 'Recon', 'Report Manager', 'Process Monitor', and a 'Run' button. Below this is a 'Selection Criteria' section with a search bar and 'Find | View All' options. The criteria fields are: '*Request ID' (1), 'System Source' (IAS 16 Revaluation), '*Business Unit' (US001), '*Book Name' (CORP), 'From Asset ID', 'Document Type', 'Process Frequency' (Always), 'Currency' (USD), and 'To Asset ID'.

This process creates the clearing accounting entries from the noncapitalized assets that have the selected system source. For each noncapital row that matches the criteria, an entry is generated in the DIST_LN table that credit the clearing account and debit the expense account according to the accounting entry template for the EX distribution type. This distribution type is available for the ADD and ADJ accounting entry templates for those template IDs that have the capitalization threshold enabled.

See "Accounting Entry Templates (*PeopleSoft FSCM 9.2: Asset Management*)".

Capitalization Threshold Summary Report Page

Use the Capitalization Threshold Summary Report page (AM_CAPSUM_RQST) to run a report to show the capitalization status of assets based upon criteria selection.

Navigation

Asset Management, Financial Reports, Capitalization Summary Report

Image: Capitalization Threshold Summary Report page

This example illustrates the fields and controls on the Capitalization Threshold Summary Report page. You can find definitions for the fields and controls later on this page.

Select criteria to report assets as they are classified according to the Capitalization Threshold process. The report displays the acquisition date, asset ID, description, quantity, tag number, serial ID, capitalized cost and noncapitalized cost.

Report Type

Select to report only the assets that are candidates for recategorization or select to report all assets.

Validation Basis

Select to report assets that are capitalized (from the cost table) or select to report both capital and noncapital assets.

Defining Fair Value Processing

This topic provides an overview of fair value processing and lists the pages used to define fair value processing for PeopleSoft Asset Management.

Pages Used to Define Fair Value Processing

Page Name	Definition Name	Navigation	Usage
Fair Value Valuation Methods	AM_FV_METHOD	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Fair Value Valuation Methods, Fair Value Valuation Methods	Define the fair value valuation methods to be used in fair value processing in accordance with FAS 157.

Page Name	Definition Name	Navigation	Usage
Fair Value Groups	AM_FV_GROUP	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Fair Value Groups, Fair Value Groups	Define fair value groups by business unit to be used in fair value processing in accordance with FAS 157.
Fair Value Templates	AM_FV_TEMPLATE	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Fair Value Templates, Fair Value Templates	Define fair value templates by business unit by selecting the fair value valuation method, valuation premise, input level and fair value group ID.

Understanding Fair Value Processing in Asset Management

Financial Accounting Standards (FAS) 157 establishes a framework for measuring the fair values of assets and liabilities and how to disclose them for the financial statements. It is effective for financial statements issued for fiscal years beginning after November 15, 2007. Asset Management supports fair value processing for international customers as well as providing the following solution in compliance with FAS 157 for U.S. companies:

- Standardized parameters when loading and capturing fair values in accordance with FAS 157.
- Appropriate fair value processing for revaluation, impairment and leases.
- Corresponding fields and prompts on the Fair Value page.

See "Capturing and Maintaining Asset Fair Value (*PeopleSoft FSCM 9.2: Asset Management*)".

- Reports for disclosure of fair values: Fair Value Activity Report and Fair Value Detail Report.
- Setup pages for fair value valuation methods, fair value groups and fair value templates.

Fair Value Valuation Methods Page

Use the Fair Value Valuation Methods page (AM_FV_METHOD) to define the fair value valuation methods to be used in fair value processing in accordance with FAS 157.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Fair Value Valuation Methods, Fair Value Valuation Methods

Image: Fair Value Valuation Methods page

This example illustrates the fields and controls on the Fair Value Valuation Methods page. You can find definitions for the fields and controls later on this page.

Fair Value Valuation Methods

Valuation Method

SetID SHARE

Valuation Method MARKET

*Description Market Approach

Comment

Market valuation method uses prices and other relevant information generated by market transactions of comparable assets.

Valuation Techniques

Personalize | Find | First 1 of 1 Last

	*Approach	*Input Type	Detail		
1	Market	Observable	Obtained from independent sources	+	-

Use this page to establish various valuation methods that are used to capture the most representative fair values for an organization, whether they be valuation techniques as defined by FAS 157 or any global techniques.

Approach

Select from the following fair value approach values to be used for the valuation method:

- *Cost* - This approach is based on the amount that is currently required to replace the service capacity of an asset (commonly referred to as current replacement cost).
- *Income* - This approach uses valuation techniques to convert future amounts (cash flows or earnings) to a single present amount (discounted). The measurement is based on the value indicated by current market expectations about those future amounts.
- *Market* - This approach uses prices and other relevant information generated by market transactions involving identical or comparable assets or liabilities (including a business).
- *Other* - This is not a FAS 157 approach, but can be used to define a method other than those that are specified in the U. S. pronouncement.

Input Type

Select from the following input types for the valuation method:

- *Observable* - inputs that reflect the assumptions that market participants use in pricing the asset or liability developed based on market data obtained from sources that are independent of the reporting entity.
- *Unobservable* - inputs that reflect the reporting entity's own assumptions about the assumptions market participants use in pricing the asset or liability developed based on the best information available in the circumstances.
- *Other* - This input type is not defined by FAS 157, but can be used to define an alternate input type for organizations that are not subject to U.S. pronouncements.

Fair Value Groups Page

Use the Fair Value Groups page (AM_FV_GROUP) to define fair value groups by business unit to be used in fair value processing in accordance with FAS 157.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Fair Value Groups, Fair Value Groups

Image: Fair Value Groups page

This example illustrates the fields and controls on the Fair Value Groups page. You can find definitions for the fields and controls later on this page.

Fair Value Groups

Fair Value Group

Business Unit US001

FV Group ID GROUP1

*Description Group 1

Comment

Group machinery used to produce semiconductors B.

Use this page to establish groups of assets for valuation processing when their valuation premise is *In Use*.

Fair Value Templates Page

Use the Fair Value Templates page (AM_FV_TEMPLATE) to define fair value templates by business unit by selecting the fair value valuation method, valuation premise, input level and fair value group ID.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Fair Value Templates, Fair Value Templates

Image: Fair Value Templates page

This example illustrates the fields and controls on the Fair Value Templates page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Fair Value Templates' page. The form is titled 'Fair Value Template' and contains the following fields and values:

- Business Unit: US001
- FV Template ID: INCOME
- *Valuation Method: MARKET
- Valuation Premise: In-Use
- Input Level: Level 1
- Group By: FV Group ID
- FV Group ID: GROUP1
- Comment: (Empty text area)

Use this page to establish default values when you add fair values from a page other than the online Fair Value page.

See "Capturing and Maintaining Asset Fair Value (*PeopleSoft FSCM 9.2: Asset Management*)".

Valuation Method

Select a valuation method defined from the Fair Value Valuation Method page. The valuation method allocates valuation techniques. This can be a valuation method according to FAS 157 or a combination of valuation techniques.

Valuation Premise

Select from the following valuation premise values:

- In Use* - Select if the asset would provide maximum value to market participants principally through its use in combination with other assets as a group (as installed or otherwise configured for use). For example, this may be the case for certain nonfinancial assets. If the highest and best use of the asset is in-use, the fair value of the asset shall be measured using an in-use valuation premise. When using an in-use valuation premise, the fair value of the asset is determined based on the price that would be received in a current transaction to sell the asset assuming that the asset would be used with other assets as a group and that those assets would be available to market participants. Generally, assumptions about the highest and best use of the asset should be consistent for all of the assets of the group within which it would be used. When selecting the *In Use* valuation premise, you must designate a Group By value.
- In Exchange* - Select if the asset would provide maximum value to market participants principally on a standalone

basis. For example, that might be the case for a financial asset. If the highest and best use of the asset is in-exchange, the fair value of the asset should be measured using an in-exchange valuation premise. When using an in-exchange valuation premise, the fair value of the asset is determined based on the price that would be received in a current transaction to sell the asset standalone. Since the asset is valued on a standalone basis using the *In Exchange* valuation premise, the Group By field is unnecessary and becomes unavailable for selection.

Input Level

Select from the following input levels:

- *Level 1* - Level 1 inputs are quoted prices (unadjusted) in active markets for identical assets or liabilities that the reporting entity has the ability to access at the measurement date.
- *Level 2* - Level 2 inputs are inputs other than quoted prices that are included within Level 1 that are observable for the asset or liability, either directly or indirectly.
- *Level 3* - Level 3 inputs are unobservable inputs for the asset or liability. Unobservable inputs are used to measure fair value to the extent that observable inputs are not available, thereby allowing for situations in which there is little, if any, market activity for the asset or liability at the measurement date.

Group By

This field is available only when the valuation premise is *In Use*. Select to group the fair value of assets by the following:

- *Cash Generating Unit*
- *FV Group ID*
- *Group Asset ID*
- *Parent ID*

FV Group ID (fair value group ID)

Select the applicable FV Group ID value, which is required when selecting to group by FV Group ID, Group Asset ID or Parent ID. The prompt values differ depending on your selection in the Group By field. For example, if you select to group fair values by Parent ID, you are prompted with the available Parent IDs from which to select. If you select *Cash Generating Unit* for the Group By field value, the FV Group ID becomes unavailable.

Defining Investment Property

This topic provides an overview of investment property and lists the pages used to identify investment property for proper accounting entry processing in PeopleSoft Asset Management.

Pages Used to Define Investment Property in Asset Management

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Categories	CATEGORY_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Categories, Categories	Establish categories as Investment Property or Property Interest, as necessary.
Installation Options - Asset Management	INSTALLATION_AM	Set Up Financials/Supply Chain, Install, Installation Options, Asset Management	Enable the Revaluation Process feature to be able to select investment property options on the Business Unit/Book Feature page and the Accounting Entry Template.
Business Unit/Book Feature	BU_BOOK_FEATURE	Set Up Financials/Supply Chain, Business Unit Related, Asset Management, Asset Management Definition, Business Unit/Book Feature	Select the investment property options within the Impairment/Revaluation Options group box (if applicable), as well as the revaluation method and the investment property transaction code.
Accounting Entry Templates	DIST_TEMPLATE_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Accounting, Accounting Entry Templates, Accounting Entry Templates	Select an investment property asset category in order to display the proper investment property accounting entries.
Revaluation Worksheet	AM_REVALUATION	Asset Management, Asset Transactions, Financial Transactions, Revaluation Worksheet, Revaluation Worksheet	Select the investment property revaluation method to retrieve the assets that should receive investment property accounting treatment.
Revaluation in Mass	AMREVAL_RQST	Asset Management, Asset Transactions, Financial Transactions, Revaluation in Mass, Revaluation in Mass	Select the investment property revaluation method to process the assets that should receive investment property accounting treatment.

Understanding Investment Property in Asset Management

In accordance with International Accounting Standards (IAS) 40, PeopleSoft Asset Management facilitates the administration of investment properties that are stored in the Asset Repository. To help organizations more easily comply with IAS 40, PeopleSoft provides:


- Ease of identification of investment property as distinguished from other assets.
- Accounting entry templates for investment property - accounting entry template and distribution type, IX, is used for investment property accumulated adjustments for nondepreciable categories.
- Reporting capabilities - investment property fields appear on the Asset Management Units/Books report (AMBU1000) and Asset Categories report (AMAS1100). Information for required disclosure of investment property fair values is provided within the Fair Value Activity Report and Fair Value Detail Report.

During the addition of property or later, you can identify the asset as investment property. This attribute can be applied at the asset level or at the asset profile or category. Identification at the category level is necessary for handling batch transactions where there is no human intervention. Investment property can be owned assets and capital leases. Property interest is an operating lease that meets the conditions to be deemed as an Investment Property. Operating leases that fall under this category are not ruled by the ordinary lease accounting rules but are treated as capital leases for accounting purposes. In other words, they are considered capital leases even if they are technically considered operating leases per FAS 13.

The following diagram summarizes the classification process and treatment of investment property for International Accounting Standards (IAS):

Image: Summarization of Investment Property Classification and Treatment

Classification process and treatment of investment property for International Accounting Standards (IAS):



Prerequisites

Before you can begin identifying investment property and make use of the delivered functionality for proper accounting treatment of investment property, you must:

1. Review IAS 40 to determine the assets that must be accounted for and reported as investment property or property interest. Determine whether they are leased assets as well and whether they require revaluation.
2. Establish categories as Investment Property or Property Interest as necessary on the Categories page.

3. Enable the Revaluation Process feature on the Installation Options - Asset Management page.

Once you enable the revaluation process at the installation level, the Investment Property option appears on the Business Unit/Book Feature page within the Impairment/Revaluation Options group box. The distribution type for investment property also appears on the Accounting Entry Template.

4. Select the investment property options within the Impairment/Revaluation Options group box (if applicable) on the Business Unit/Book Feature page. These include options for the revaluation method and the investment property transaction code.

Categories Page

Use the Categories page (CATEGORY_DEFN) to establish categories as Investment Property or Property Interest, as necessary.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Categories, Categories

The Categories page provides investment property indicators that enable proper accounting treatment and generate investment property reporting detail for required disclosure.

Selection of the depreciable status and investment property options on this page dictates which accounting entries to display in the accounting entry template.

See [Combination Editing Options Page](#).

Creating Accounting Entries for Investment Property

The Asset Management accounting entry templates accommodate accounting entries that are required for investment property. When selecting an asset category (for the accounting entry template) that has investment property options selected, the Investment Property distribution type (IP) directs related accounting entries for all processes to the investment property account. This is applicable for all of the templates where a fixed asset account appears.

See [Accounting Entry Templates Page](#).

See "Understanding Asset Information Flow (*PeopleSoft FSCM 9.2: Asset Management*)".

Enabling the Revaluation Process for Investment Property

If you decide to measure investment properties using the fair value model, PeopleSoft Asset Management provides a calculation to reflect the gain or loss that is generated by the fair value fluctuation over time. To enable revaluation for investment properties, the following setup is required:

1. Enable the Revaluation Process feature within the Installation Options - Asset Management page.
2. Enable the specific investment property options for Impairment and Revaluation processes on the Business Unit/Book Feature page.

Enable Revaluation Installation Option

Select the Revaluation Process check box. The selection of this check box makes investment property options visible on the Business Unit/Book Feature page for impairment and revaluation processing.

See "Installation Options - Asset Management Page (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

Enable Investment Property Impairment and Revaluation Options

Enable the Impairment/Revaluation Options that deal with the investment property treatment: The enhancement here consists in two new fields, the first to check if the book will enable the Investment Property revaluation and the second to assign the corresponding Transaction Code associated to that kind of transaction

- Investment Property - select to enable investment property revaluation for a book within the business unit.
- Revaluation Method - select the *Inv Prop* (investment property) field.
- Inv. Property Trans. Code - select the investment property transaction code.

See [Creating PeopleSoft Asset Management Business Units](#) and see [Business Unit/Book Feature Page](#).

Enable Revaluation Worksheet for Investment Property

As with other assets, use the Revaluation Worksheet to revalue investment properties. Select the *Inv Prop* revaluation method on the Revaluation Worksheet to retrieve all of the investment property assets. When making this selection, these assets are retrieved even if the Asset Category field is left blank.

See "Revaluing Assets Using the Revaluation Worksheet (*PeopleSoft FSCM 9.2: Asset Management*)".

Enabling Combination Editing

This topic provides an overview of combination editing and lists the pages used to define combination edit processing for PeopleSoft Asset Management.

Pages Used to Enable Combination Editing in Asset Management

Page Name	Definition Name	Navigation	Usage
Business Unit/Book Definition	BU_BOOK_DEFN_01	Set Up Financials/Supply Chain, Business Unit Related, Asset Management, Asset Management Definition, Business Unit/Book Definition	If the Create Accounting Entries check box is selected, the ChartField Edit Options group box appears. Select to receive a warning message, to reject the transaction or to perform no ChartField combination edits for the business unit and book.

Page Name	Definition Name	Navigation	Usage
Combination Editing Options	AM_CEDT_SSRC	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Combination Editing Options, Combination Editing Options	Select the system source or sources of the processes for which you want to enable ChartField combination editing.

Understanding Combination Editing in Asset Management

Asset Management leverages the existing common setup for valid and invalid ChartField combinations and is consistently applied to all transactions that generate accounting entries for General Ledger.

See "Understanding ChartField Combination Editing (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

ChartField combination editing is applicable for books that are associated to a GL ledger. Set ChartField combination editing options at the business unit/book level. These settings are applied upon saving certain online components, at which time the Combo Edit processor is invoked (FS_COMBO_EDIT). If the ChartField combination fails validation, an additional Combo Edit page appears within the online component that displays the error message. Depending upon the combo edit options settings, the page may be saved with errors, rejected, or bypass combination editing.

Note: As account values are not entered in the asset transactions themselves, it is the fixed asset (FA) accounts that are defined for the transaction type, cost type, category and accounting entry template that are used in validating ChartField combinations.

For batch Asset Management transactions, the process invokes the Combination Editing Options setup. Specify the system sources that are to be excluded from ChartField combination editing validation (generally includes sources wherein ChartField combinations may have already been validated).

This table presents the Asset Management components for which combination editing is available:

Event	Type of Processing	Components/ Pages/ Processes
Add assets.	Online Batch	Express Add (ASSET_ENTRY_00) page. Transaction Loader process (AMIF1000). Asset Basic Add (ASSET_GENERAL_01) page.
Adjust, revalue, recategorize, or transfer assets and costs.	Online Batch	Cost Adjust/Transfer Asset (COST_BAL) page. Transaction Loader process (AMIF1000).
Retirements and reinstatements.	Online Batch	Retire/Reinstate Asset (RETIRE) component. Transaction Loader process (AMIF1000)

Event	Type of Processing	Components/ Pages/ Processes
Leased assets.	Online	Leased Assets, Express Add (LEASE_ENTRY) page. Update Lease Information (LEASE_ENTRY) page. Transfer Operating Lease (LEASE_OPR_TFR) page.
Consolidate and unitize assets.	Online	Consolidate Assets (ASSET_CONSOL) page. Unitize Assets (ASSET_UNIT) page.
Copy an asset.	Online	Copy Existing Asset (COPY_ASSET) page.
Review financial entries.	Online	Review Financial Entries (ASSET_DIST).
Review operating leases.	Online	Review Operating Leases (NF_DIST_LN).
Review expense entries.	Online	Review Expense Entries (ASSET_NF_DIST).
Impairment, Revaluation, Disposal	Batch	Transaction Loader process (AMIF1000)
Update noncapitalized costs.	Batch	Update Non-capitalized Costs (NON_CAP_COSTS) page.

Business Unit/Book Definition Page

Use the Business Unit/Book Definition page (BU_BOOK_DEFN_01) to if the Create Accounting Entries check box is selected, the ChartField Edit Options group box appears.

Select to receive a warning message, to reject the transaction or to perform no ChartField combination edits for the business unit and book.

Navigation

Set Up Financials/Supply Chain, Business Unit Related, Asset Management, Asset Management Definition, Business Unit/Book Definition

Image: Business Unit/Book Definition Page

This example illustrates the fields and controls on the Business Unit/Book Definition Page. You can find definitions for the fields and controls later on this page.

The screenshot displays the 'Business Unit/Book Definition' page. At the top, there are tabs for 'AM Business Unit Definition', 'Business Unit/Book Definition', 'Business Unit/Book Feature', and 'Interface Options'. The main content area is titled 'Unit JPN01 JAPAN OPERATIONS'. Below this, there is a 'Book' section with fields for 'Book Name' (CORP_USD), 'Book Type' (Corporate Book), and a checked 'Book is Required' option. The 'Book Options' section includes 'Currency' (USD), 'Rate Type' (CRRNT), 'Calendar' (J1), 'Capitalize Limit' (Amount), and 'Lease Cap Min'. The 'Accounting Entry Options' section has 'Create Accounting Entries' checked, 'GL Business Unit' (JPN01), 'Ledger Group' (RECORDING), 'Budget Ledger Group', 'Account Entry Template ID' (DEFAULT), 'Statutory Book', 'Ledger' (CORPORATE), and 'Budget Ledger'. A 'Chartfield Edit Option' section offers radio buttons for 'No Edits', 'Warning', and 'Reject w/ edit error'. A 'Comment' field is at the bottom.

See [Business Unit/Book Definition Page](#).

Warning! Changes to the original ChartField combination editing rules may result in invalid ChartField combinations for subsequent Asset Management processes, such as depreciation. Some transactions such as retirements cannot be done at all (if the Combination Edit option is set to Reject) if you invalidated previously accepted combinations. A similar situation occurs when you deactivate a ChartField that is assigned to an asset. In this case, you would have to reactivate the ChartField and include those combinations again, or set the Combination Edit Option to Warning or No Edits.

Combination Editing Options Page

Use the Combination Editing Options page (AM_CEDT_SSRC) to select the system source or sources of the processes for which you want to enable ChartField combination editing.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Combination Editing Options

Image: Combination Editing Options Page

This example illustrates the fields and controls on the Combination Editing Options Page. You can find definitions for the fields and controls later on this page.

Combination Editing Options

SetID **SHARE**

Template **AMEDIT**

Description **AM ComboEdit Template**

Exceptions		Personalize Find	First 1-4 of 4 Last
	System Source	Description	
1	BAM	AM Batch	+ -
2	IMP	Asset Impairment	+ -
3	PAM	AM Online Entry Page	+ -

Template

The combination editing process uses the record template for structural information to perform ChartField combination edits. The record templates have a unique name that is applicable to a particular PeopleSoft application.

Exceptions

System Source

Enter the trusted sources that do not need ChartField combination validation. Select the system source code as it appears in the interface tables.

Defining Document Sequencing

Use the Document Type Template (AM_DOCTYPE_TMPL) component to define document sequencing.

This topic provides an overview of document sequencing for PeopleSoft Asset Management, lists pages used to set up document sequencing, and describes how to define Document Sequence Type Templates.

Pages Used to Define Document Sequencing for PeopleSoft Asset Management

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Document Type	DOC_TYPE	Set Up Financials/Supply Chain, Common Definitions, Document Sequencing, Document Type	Define asset management document types using this page.
Journal Generator Template - Defaults	JRNL_GEN_DEFAULTS	General Ledger, Journals, Subsystem Journals, Journal Generator Template, Defaults	Assign a document type to the accounting entries that PeopleSoft Asset Management generates. The Journal Generator Application Engine process (FS_JGEN) uses this information to assign a document sequence number when you create journals through the Journal Generator process.
Journal Generator Template - Summarization	JRNL_GEN_SUM	General Ledger, Journals, Subsystem Journals, Journal Generator Template, Summarization	Select Retain Detail in the How Specified Option group box to retain and pass the document sequence numbers to General Ledger.
Document Type Template	AM_DOCTYPE_TMPL	Set Up Financials/Supply Chain, Product Related, Asset Management, Accounting, Document Type Template, Document Type Template	Assign document types to each accounting entry type in Asset Management.

Understanding Document Sequencing for PeopleSoft Asset Management

Statutory requirements in some countries require that all financial transactions (documents) be classified into different transaction types, and that within each transaction type, all documents entered be numbered sequentially. The document sequencing feature helps you maintain established business practices by meeting both of these requirements.

Document sequencing is available for transactions that you create either online or through background (batch) processing. When you activate document sequencing, the system automatically assigns a sequence number to each document (invoice, voucher, journal, and so on) that you create. You can also enter sequence numbers manually. When you delete, change, or unpost a document, the system may generate additional document sequence numbers, as appropriate.

PeopleSoft Asset Management uses the Document Type Template (AM_DOCTYPE_TMPL) page to add and maintain document types relevant to specific asset categories or transactions. Before you can establish a document type template, you must first establish the following:

- The Document Sequence Range (SEQ_RANGE) page maintains the sequence number range; the range is user-defined, and often based on an annual (AN) or monthly (MN) counter.

- Use the Journal Code (JRNL_CODE) page to define journal codes, specify sequence ranges, and determine how document sequence numbers are assigned for each journal code.
- The Document Type (DOC_TYPE) page establishes document sequencing options for PeopleSoft Asset Management business processes that generate financial transactions. This is the equivalent of the Journal Type used by General Ledger.

Document sequencing occurs at either the journal code level or the document type level within a journal code. If sequencing occurs at the journal code level, all document types within a journal code share the same sequence numbers. If sequencing occurs at the document type level, each document type has its own sequence numbers. This is determined by the Sequence By field on the Journal Code table. In PeopleSoft Asset Management, this is defined on the Document Type Template (AM_DOCTYPE_TMPL) page.

Document sequencing can either be set to manual or automatic. In the case where the document sequence allows for manual entry, the system validates the number to ensure that the number falls within the appropriate range and is unique. If the option has been set to automatic, the system selects the next available number in the sequence. If the option is set to manual without entering a value, an error is generated. In cases where the option is set to manual, and a batch process inserts the sequence number, the batch process generates the numbers sequentially and the numbers can not be altered.

As transactions with document sequencing occur through online processing and from batch processes such as the transaction loader process (AMIF1000), the PeopleSoft Asset Management document sequencing table (AM_DOC_SEQ) stores the transaction data by row. This table joins with the PS_DIST_LN table so that the entries are created in General Ledger. If journals are created through the Journal Generator process from subsystem accounting entries, document sequence numbers are already assigned when the option to retain detail is selected. Assigned document sequence numbers are carried forward to the journal lines. When the summarization option is selected, document sequencing field values are left blank.

The document sequence page (AM_DOC_SEQ) is used throughout the PeopleSoft Asset Management application where a financial transaction occurs: Express Add, Basic Add, Cost Transfer/Adjust, Leases, Copy Assets, Adjust Accumulated Depreciation, Update/Delete Pending Transactions, Impairment, and Retirement. Each page displays a document sequencing tab for the entry and allows you to view, enter or override document sequence information.

When using multiple ledger groups with multiple ledger assigned, the following rules apply: If the *Keep Ledgers in Sync* (KLS) option is enabled, the ledger group will maintain the same sequencing number across ledgers. Only the primary ledger group/ledger combination will have a unique sequencing number. If KLS is not enabled, then both ledgers assigned to the ledger group have different sequence numbers. If multiple ledger groups are assigned to a business unit, even with KLS on, the ledger groups would have different sequence numbers. They can independently have KLS enabled or not.

This table shows the details associated with each component, page or process where access to document sequencing is available.

Event	Type of Processing	Components/ Pages/ Processes
Add assets.	Online Batch	Express Add (ASSET_ENTRY_00) page. Transaction Loader process (AMIF1000). Asset Basic Add (ASSET_GENERAL_01) page.
Adjust, revalue, recategorize, or transfer assets and costs.	Online Batch	Cost Adjust/Transfer Asset (COST_BAL) page. Transaction Loader process (AMIF1000).
Retirements and reinstatements.	Online Batch	Retire/Reinstate Asset (RETIRE) component. Transaction Loader process (AMIF1000)
Lease assets.	Online	Leased Assets, Express Add (LEASE_ENTRY) page.
Copy an asset.	Online	Copy Existing Asset (COPY_ASSET) page.
Change or delete a pending transaction.	Online Batch	Change/Delete Pending Transactions (PEND_TRANS_UPD_DEL) page.
Adjust accumulated depreciation.	Online	Adjust Accumulated Depr (DEPR_ACCUM_ADJ).
Depreciation, reverse depreciation, prior depreciation.	Batch	Depreciation close application engine process (AM_DPCLOSE).
Allocate depreciation.	Batch	Depreciation Allocation process (AMALLOC).
Define tax and depreciation criteria (only when transaction involves accounting).	Online	Define Tax/Depr Criteria (BOOK_DEFN).
Review financial entries.	Online	Review Financial Entries (ASSET_DIST).
Adjust for inflation.	Batch	Adjust for inflation (AMDPINFL) process.
Reverse depreciation adjustment.	Batch	Depreciation close application engine process (AM_DPCLOSE).
Lease payment, reverse lease payments.	Batch	Depreciation close application engine process (AM_DPCLOSE).
Impairment, Revaluation	Batch	Transaction Loader process (AMIF1000)

A Parent asset that disposes, transfers or makes recategorizations to its children can have a different document type from its defaulted one. You can manually override it but the child assets inherit the parent asset document type. In such a case, the document type needs to be defined as automatically generated.

Group assets are treated as one entity for the purpose of depreciation, but as multiple entities for all other purposes. Therefore, these assets do not generate a different sequence number at asset level. For any other transactions, they are treated as ordinary assets. AMDPCGRP defines the sequence to be given to that transaction based on the accounting entry template selected. For transfers by Group ID, the system generates sequenced numbers for the transfer out transaction. The transfer in transaction is handled by GL in the same manner as a regular InterUnit transaction.

No transaction detail is carried by individual composite members. All transaction detail, including any gain or loss accrued upon retirement, is rolled up to the composite asset level. Once this roll up occurs, no transaction detail is retained by composite members. Composite assets will be treated as ordinary assets but not their members. These do not generate sequenced numbers.

Joint Ventures are not supported for participant business units.

Prerequisites

Before you can begin using the Document Sequencing feature in PeopleSoft Asset Management, you must:

1. Enable document sequencing at the installation level.

The system does not perform any document sequencing functions unless you select the Document Sequencing option on the Installation Options - Overall page.

2. Enable document sequencing at the PeopleSoft General Ledger business unit level.

Once you enable document sequencing at the installation level, activate it for designated General Ledger business units on the General Ledger Definition page.

3. Specify a document sequence range.
4. Define the journal types and journal codes.
5. Define the document types.

Document sequencing uses the following components:

- Journal Type (JRNL_TYPE)
- Journal Code (JRNL_CODE)
- Document Types (DOC_TYPE)
- Sequence Range (SEQ_RANGE)

See "Setting Up Application-Specific Installation Options (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

See "Understanding Document Sequencing (*PeopleSoft FSCM 9.2: Global Options and Reports*)".

See "Defining General Ledger Business Units (*PeopleSoft FSCM 9.2: General Ledger*)".

See [Understanding Asset Management Business and Cash Generating Units](#).

Document Type Template Page

Use the Document Type Template page (AM_DOCTYPE_TMPL) to assign document types to each accounting entry type in Asset Management.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Accounting, Document Type Template, Document Type Template

Image: Document Type Template page

This example illustrates the fields and controls on the Document Type Template page. You can find definitions for the fields and controls later on this page.

Document Type Template

SetID SHARE

Asset Category AUTO

Transaction Code

Default Document Type

*Add <input type="text" value="AM-ADD"/>	*PDP <input type="text" value="AM-PDP"/>
*Adjustment <input type="text" value="AM-ADJ"/>	*PDP Reverse <input type="text" value="AM-PDR"/>
*Depreciation <input type="text" value="AM-DPR"/>	*Retire <input type="text" value="AM-RET"/>
Depr Reversal <input type="text" value="AM-DRR"/>	*Reinstate <input type="text" value="AM-REI"/>
*Lease Payment <input type="text" value="AM-LPY"/>	*Transfer <input type="text" value="AM-TSF"/>
*Lease Pay Rev <input type="text" value="AM-LPR"/>	*Recategorize <input type="text" value="AM-RECAT"/>
Revaluation <input type="text" value="AM-REVAL"/>	Reserve <input type="text" value="AM-RAD"/>
Impairment <input type="text" value="AM-IMP"/>	Inflation <input type="text" value="AM-INF"/>
Impair Reverse <input type="text" value="AM-IMR"/>	

Assign document types to be used by default by document sequencing for asset categories and asset transaction codes.

Note: If you are using revaluation, you need to define a template for the revaluation transaction code.

Setting Up Depreciation Processing

Setting Up Depreciation Processing

This topic provides an overview of depreciation processing and discusses how to:

- Set up depreciation calendars.
- Set up depreciation conventions.
- Set up depreciation schedules.
- Define depreciation terms.
- Define depreciation bonus information.
- Define depreciation limits.
- (DEU) Set up multi-shift codes for German depreciation processing.
- Enable option to stop negative depreciation.

Understanding Depreciation Processing

PeopleSoft Asset Management supports all common methods for depreciation processing and corresponds to Generally Accepted Accounting Principles (GAAP) and International Accounting Standards (IAS). Commonly-used depreciation functionality is delivered and ready to be personalized for your enterprise needs. How you define your depreciation processing here determines the depreciation calculation conventions, schedules, terms, and limits for your assets, as well as setup for compliance with periodic asset depreciation legislative and reporting requirements.

Some assets may be depreciated on an annual basis, while others accumulate depreciation monthly or quarterly. Defining depreciation calendars enables you to apply periodic depreciation allocations to assets.

Defining depreciation conventions enables you to establish the start date for asset depreciation. This is used in conjunction with an asset's placed-in-service date to calculate the correct depreciation amount for an asset.

A depreciation schedule is a special type of depreciation method. Depreciation schedules are tables specifying the percentage of depreciation expensed for each period and must be defined for assets using this treatment.

Depreciation terms are typically used in global environments where it is necessary to adjust depreciation calculations to meet local requirements.

Depreciation bonus definitions allow setup of federal or local legislation parameters. These definitions are assigned to assets or asset profiles for automated application of depreciation bonuses for qualifying assets. PeopleSoft delivers depreciation bonus definitions for prior legislation but also enables you to add and configure your own bonus definitions to meet new legislation or other needs that are specific to your organization.

Usually, depreciation limits are imposed by local taxing authorities. Defining depreciation limits enables you to apply the limits to assets accordingly.

Multi-shift codes are used in Germany to accelerate asset depreciation by specifying usage across multiple production shifts. Depreciation is increased as useful life is decreased. Enabling multi-shift codes applies this treatment to depreciation calculations.

In compliance with IAS and GAAP, PeopleSoft provides the option to stop the depreciation calculation in the event the salvage value of an asset exceeds that of its Net Book Value.

Setting Up Depreciation Calendars

To set up depreciation calendars, use the Detail Calendar (DETAIL_CALENDAR) component.

This topic lists the pages used to define calendars for depreciation allocation.

Page Used to Set Up Depreciation Calendars

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Calendar Periods - Depreciation	DETAIL_CALENDAR2	Set Up Financials/Supply Chain, Common Definitions, Calendars/Schedules, Detail Calendar, Calendar Periods, Depreciation	Define calendar periods for allocation of depreciation.

Setting Up Depreciation Conventions

To set up depreciation conventions, use the Depr Convention Builder (CONV_BLDR_PNLG), Depr Convention Definition (DEPR_CONVENTION), Depr Convention Multiple Copy (CONV_COPY_ALL_COMP), and Depr Convention Single Copy (CONV_COPY_PNLG) components.

This topic provides an overview of depreciation conventions and discusses how to:

- Generate conventions.
- Modify conventions.

Pages Used to Set Up Depreciation Conventions

Page Name	Definition Name	Navigation	Usage
Convention Builder	CONV_BLDR_PNL	Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Convention Builder	Create a depreciation convention. Generate depreciation conventions based on monthly accounting calendars.
Convention Definition	CONVENTION_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Convention Definition, Convention Definition	Modify a convention that you have built, or add a new convention and enter all the dates associated with it. It is recommended that you use the Convention Builder page to add a new convention.
Depreciation Convention Single Copy	CONV_COPY_PNL	Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Convention Single Copy	Copy one convention from a SetID or calendar to another SetID or calendar.
Depreciation Convention Multiple Copy	CONV_COPY_ALL_PAGE	Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Convention Multiple Copy	Copy all conventions associated with a SetID or calendar to another SetID or calendar.

Related Links

"Understanding Depreciation Processing (*PeopleSoft FSCM 9.2: Asset Management*)"

Understanding Depreciation Conventions

Depreciation conventions, in combination with an asset's placed-in-service date, determine when depreciation starts. For example, where a following month convention is used and an asset is placed in service on February 1, depreciation begins on March 1. PeopleSoft Asset Management delivers a wide selection of depreciation tables, including depreciation conventions. Before you set up your own Depreciation Conventions table, review the delivered tables to determine if you can use them as delivered or if modifications are required.

PeopleSoft Asset Management provides a series of pages that enable you to:

- Define a depreciation convention and automatically generate start, end, and begin depreciation dates based on a selected calendar.
- Modify the dates associated with a convention without regenerating it.
- Copy conventions associated with a SetID or calendar:
 - Copy *one* convention associated with a SetID or calendar to another SetID or calendar.

- Copy *all* conventions associated with a SetID or calendar to another SetID or calendar.

Convention Builder Page

Use the Convention Builder page (CONV_BLDR_PNL) to create a depreciation convention.

Generate depreciation conventions based on monthly accounting calendars.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Convention Builder

Image: Convention Builder page

This example illustrates the fields and controls on the Convention Builder page. You can find definitions for the fields and controls later on this page.

Convention Builder

Convention

SetID: SHARE
 Calendar ID: 01Monthly
 Convention: FY
 Description: Full Year

Periods in a Year: 12

Period Options

Middle of Begin Depr Period
 Actual Days of Period

Generate Options

Convention Type: ▼

Begin Depr Date Options

Which Day:
 Which Month:
 Summary Periods:

Calendar Options

Full Calendar
 Portion of Calendar

From Year:
 To Year:

Generate

Begin Depreciation Date				Personalize Find	First	1-26 of 26	Last
	*Begin Date	*End Date	*Begin Depr Date				
1	01/01/1990	12/31/1990	01/01/1990	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
2	01/01/1991	12/31/1991	01/01/1991	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
3	01/01/1992	12/31/1992	01/01/1992	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
4	01/01/1993	12/31/1993	01/01/1993	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
5	01/01/1994	12/31/1994	01/01/1994	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
6	01/01/1995	12/31/1995	01/01/1995	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
7	01/01/1996	12/31/1996	01/01/1996	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
8	01/01/1997	12/31/1997	01/01/1997	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
9	01/01/1998	12/31/1998	01/01/1998	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
10	01/01/1999	12/31/1999	01/01/1999	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
11	01/01/2000	12/31/2000	01/01/2000	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
12	01/01/2001	12/31/2001	01/01/2001	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
13	01/01/2002	12/31/2002	01/01/2002	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
14	01/01/2003	12/31/2003	01/01/2003	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>
15	01/01/2004	12/31/2004	01/01/2004	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>	<input type="checkbox"/>

Period Options

Select *Mid Period* or *Days*. Use *Days* to begin depreciation based on the value specified in the Begin Date field. Use *Mid Period* for mid-month and mid-quarter conventions.

Generate Options

This table summarizes how the system determines the begin depreciation date for each convention type, and indicates which fields can be overridden:

Convention Type	Begin Depreciation Date
Mid Month	15 appears by default for Which Day; the begin depreciation date is day 15 of the calendar period. You can override Which Day.
End of Month	Uses the end date of the month as the begin depreciation date. You cannot override this.
End of Quarter	Uses the end date of the quarter as the begin depreciation date. You cannot override this.
End of Year	Uses the end date of the year as the begin depreciation date. You cannot override this.
Following Month	Adds one day to the end day of the month, and identifies this as the begin depreciation date. You cannot override this.
Full Year	Uses the current day of the current month as the begin depreciation date. You cannot override this.
Half Year	1 appears by default for Which Day; 7 appears by default for Which Month, so day 1 of period 7 in the calendar is the begin depreciation date. You can override Which Day and Which Month.
Mid Quarter	15 appears by default for Which Day; 2 appears by default for Which Month, so day 15 of the second month in the quarter is the begin depreciation date. You can override Which Day only.
User Defined	No defaults are provided. Specify values for Which Day, Which Month, and Summary Periods.

Begin Depr Date Options

Enter the options for which to begin depreciation for those conventions that you can override:

Which Day

Enter the numerical day of the month when depreciation is to begin.

Which Month

Enter the numerical month when depreciation is to begin.

Summary Periods

Specify how many months will be grouped or summarized into one period of the year. For example, if the Summary Periods value is 1, there will be 1 month per 1 period and there will be a total of 12 periods in one year. If the Summary Periods value is

3, there will be 3 months in 1 period and there will be a total of 4 periods in one year.

An example of beginning depreciation date options is as follows:

- Summary Periods = 3 (three months in one period)
- Which Month = 2 (second month within the period)
- Which Day = 15 (15th day of the second month)

Period	Begin Date	End Date	Begin Depr Date
Period 1	January 1, 2009	March 31, 2009	February 15, 2009
Period 2	April 1, 2009	June 30, 2009	May 15, 2009
Period 3	July 1, 2009	September 30, 2009	August 15, 2009
Period 4	October 1, 2009	December 31, 2009	November 15, 2009
Period 5 (next year)	January 1, 2010	March 31, 2010	February 15, 2010

Calendar Options

Full Calendar

Select to build conventions for all years. When selecting this option, the From Year and To Year fields are unavailable.

Portion of Calendar

Select to build conventions for the years that you specify. When selecting this option, supply the From Year and To Year fields.

Click the Generate button to build the conventions based upon the options that you selected.

Convention Definition Page

Use the Convention Definition page (CONVENTION_DEFN) to modify a convention that you have built, or add a new convention and enter all the dates associated with it.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Convention Definition, Convention Definition

Select System Maintained to use standard depreciation conventions that are delivered with and maintained by the PeopleSoft system.

Note: You cannot enter the *from* date, *to* date, or the *begin depreciation* date for system-maintained depreciation conventions.

Setting Up Depreciation Schedules

To set up depreciation schedules, use the Depreciation Schedule Definition (DEPR_SCHEDULE_DEFN) component.

This topic provides an overview of depreciation schedules and discusses how to define depreciation schedules.

Page Used to Set Up Depreciation Schedules

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Depreciation Schedules	DEPR_SCHEDULE_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Schedules	Add or modify depreciation tables.

Understanding Depreciation Schedules

There are several different methods for calculating depreciation. Each depreciation method is an equation by which depreciation is calculated. In most methods, the same equation is used to calculate depreciation for each period. A depreciation schedule is a special type of depreciation method. Depreciation schedules are tables specifying the percentage of depreciation expensed for each period. Currently, the PeopleSoft system delivers schedules (DEPR_SCHEDULE_TBL system table) for the following standard IRS depreciation methods:

- Declining balance with straight-line switch:
 - 200 percent
 - 175 percent
 - 150 percent
 - 125 percent
- Sum-of-the-years' digits.
- ACRS (Accelerated Cost Recovery System), GDS (General Depreciation System), ADS (Alternative Depreciation System).
- MACRS (Modified Accelerated Cost Recovery System), GDS, ADS.

Note: Standard depreciation schedules cannot be used for short tax year processing. For short tax year processing, you need to set up special schedules that have the short tax year worked into them.

PeopleSoft Asset Management depreciation schedules are based on the percentage depreciation tables found in IRS Publication 534. You can modify existing depreciation schedules or add new schedules, by using the Depreciation Schedule page. On the Depreciation Schedules page, the method is DB150 with a switch to straight line. The in-service period for each year of the asset's life is the key to determining the percentage of depreciation allowed for any one year. For example, suppose that your organization runs

on a monthly calendar and places an asset in service in January 1997. View Year of Life 1, In-Service Period 1 to find the percentage allowed in the first year; view Year of Life 2, In-Service Period 1 to find the percentage allowed for the second year, and so on.

Schedules Page

Use the Schedules page (DEPR_SCHEDULE_DEFN) to add or modify depreciation tables.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Schedules

Image: Schedules page

This example illustrates the fields and controls on the Schedules page. You can find definitions for the fields and controls later on this page.

Schedules

SetID SHARE

Schedule Code DB125/STL

Asset Life 36 Periods

Schedule Find | View All First 1 of 1 Last

*Effective Date + -

*Description + -

Specific Convention

Schedule Periods Personalize | Find | First 1-47 of 47 Last

*In Service Period	*Year of Life	Depreciation Percent (%)	
1	1	41.666667	+ -
2	1	38.194445	+ -
3	1	34.722221	+ -
4	1	31.250000	+ -
5	1	27.777779	+ -
6	1	24.305555	+ -
7	1	20.833333	+ -
8	1	17.361111	+ -
9	1	13.888889	+ -
10	1	10.416667	+ -
11	1	6.944445	+ -
12	1	3.472222	+ -
1	2	29.166667	+ -
2	2	29.666667	+ -
3	2	30.128205	+ -

Specific Convention

Select to apply a particular convention. The page refreshes and displays the Convention list box from which to choose the depreciation convention.

Convention

This field appears when selecting the Specific Convention check box. Select the convention that you want to use.

Note: The schedule periods that you set up should reflect the periods set up in your calendar.

Related Links

"Understanding Depreciation Processing (*PeopleSoft FSCM 9.2: Asset Management*)"

Defining Depreciation Terms and Rates

To set up depreciation terms, use the Terms Definition (DEPR_TERMS_DEFN) component, the Rate-User Defined (UD_DEPR_RATE) component, and the Period Allocation (RUN_AMCALLOC) component.

This topic lists the pages used to set up depreciation terms and rates and discusses how to define depreciation terms.

Pages Used to Define Depreciation Terms

Page Name	Definition Name	Navigation	Usage
Depreciation Terms	DEPR_TERMS_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Terms Definition	Enter terms to be applied to depreciation in a global environment. These terms are used to alter depreciation calculations so that they comply with specific country requirements. Terms defined at this level are available to be selected when you are specifying depreciation methods and when you have enabled global options.
Rate-User Defined	UD_DEPR_RATE_TBL	Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Rate-User Defined	Establish rates by useful life.
Life and Rate Information	MR_AM_LIFERATE	Click the Life and Rate Information button from the Rate-User Defined page.	View and update rate by useful life.

Page Name	Definition Name	Navigation	Usage
AM Period Allocation	RUN_AMCALLOC	Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Period Allocation, AM Period Allocation	Create depreciation expense allocation tables.

Depreciation Terms Page

Use the Depreciation Terms page (DEPR_TERMS_DEFN) to enter terms to be applied to depreciation in a global environment.

These terms are used to alter depreciation calculations so that they comply with specific country requirements. Terms defined at this level are available to be selected when you are specifying depreciation methods and when you have enabled global options.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Terms Definition

Image: Terms Definition page

This example illustrates the fields and controls on the Terms Definition page. You can find definitions for the fields and controls later on this page.

Terms Definition

SetID SHARE

Depreciation Special Terms SONDER_AFA

Depreciation Terms Find | View All First 1 of 1 Last

*Effective Date 01/01/1900

*Description Germany - Sonderabschreibung - 20% in 4 Years

Special Terms		Personalize Find	First 1-4 of 4 Last
	*Year of Life	Depreciation Percent (%)	
1	1	5.000000	+ -
2	2	5.000000	+ -
3	3	5.000000	+ -
4	4	5.000000	+ -

Depreciation terms are used to adjust depreciation calculations so that they comply with specific country requirements. Using additional terms affects how depreciation is calculated:

Term	Depreciation
Special	Depreciation x Rate

Term	Depreciation
Accelerated	Depreciation x Rate
Initial	Cost x Rate
Increase	Depreciation x Rate

Related Links

"Understanding Depreciation Processing (*PeopleSoft FSCM 9.2: Asset Management*)"

Defining Depreciation Bonus Information

To set up depreciation bonus information, use the Depreciation Bonus (AM_DEPR_BONUS) component.

Use the Depreciation Bonus component to define Depreciation Bonus values. Depreciation Bonus values are then selected at the Asset level or Asset Profile level for qualifying assets based on depreciation bonus legislation.

This section discusses how to define depreciation bonus information.

Page Used to Define Depreciation Bonus

Page Name	Definition Name	Navigation	Usage
Depreciation Bonus Info	AM_DEPR_BONUS_INFO	Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Depreciation Bonus, Depreciation Bonus Info	Modify the delivered Bonus Depreciation options, if necessary, or add new Bonus Depreciation values to accommodate depreciation bonus legislation changes.

Depreciation Bonus Page

Use the Depreciation Bonus page (AM_DEPR_BONUS_INFO) to modify the delivered Bonus Depreciation options, if necessary, or add new Bonus Depreciation values to accommodate depreciation bonus legislation changes.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Depreciation Bonus, Depreciation Bonus

Image: Depreciation Bonus Page

This example illustrates the fields and controls on the Depreciation Bonus Page. You can find definitions for the fields and controls later on this page.

Use the Depreciation Bonus Info page to add new depreciation bonus values or to modify existing values to accommodate new legislation. You are then able to assign the Depreciation Bonus definitions to assets or asset profiles.

See "Book - Tax Page (*PeopleSoft FSCM 9.2: Asset Management*)".

See [Asset Profiles - Tax Page](#).

Although PeopleSoft Asset Management delivers several depreciation bonus values based on prior legislation, the Depreciation Bonus component gives you the flexibility to create your own Depreciation Bonus definitions in order to accommodate individual organization needs as well as new legislative changes.

Depreciation Bonus

Select (or supply) the Depreciation Bonus value to modify or add a new Depreciation Bonus value. The value can be 0 to 9 or A to Z.

Use bonus percent range

Select this check box to use a range of bonus percent values. When selected, the Bonus Percent To field appears.

Bonus Percent

Enter the percent amount of the depreciation bonus to be applied to the book(s) for a given asset profile. The amount depends on the Depreciation Bonus type, the acquisition date and in service

date of the asset as well as state or local application of the depreciation allowance. For example, if your state adopted the bonus depreciation as a percentage of the Federal percentage, the amount may be calculated as an amount other than the federally allowed percentage.

Acquisition & In-Service Dates

Use same date for both

Select this check box when the asset acquisition date range is the same as the in-service date range. When selected, only one row appears for Acquisition & In-Service date range.

Acquisition & In-Service From

Enter the first date of the allowable range from which the asset is to be acquired and in-service in order to take advantage of the depreciation bonus.

Acquisition Date to

Enter the end of the allowable acquisition date range in order to take advantage of the depreciation bonus. This field becomes Acquisition & In-Service To when the Use same date for both field is selected.

In-Service Date from and In-Service Date to

Enter the allowable in-service date range for assets to take be able to take advantage of the depreciation bonus. This row appears when the Use same date for both check box is deselected.

Defining Depreciation Limits

To set up depreciation terms, use the Limits (DEPR_LIMIT_DEFN) component.

Depreciation limits are used to specify the maximum amount of depreciation that you can expense on your assets for each year of life.

This topic discusses how to define depreciation limits.

Page Used to Define Depreciation Limits

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Depreciation Limits	DEPR_LIMIT_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Limits	Specify the maximum amount of depreciation that you can expense on your assets for each year of life. As a rule, depreciation limits are specified by tax authorities.

Depreciation Limits Page

Use the Depreciation Limits page (DEPR_LIMIT_DEFN) to specify the maximum amount of depreciation that you can expense on your assets for each year of life.

As a rule, depreciation limits are specified by tax authorities.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Limits

If you choose, you can use the delivered Depreciation Limit table to reduce the number of table setup tasks. PeopleSoft Asset Management delivers limits based on U.S. tax law. Currently, this defines depreciation limits for luxury automobiles.

Related Links

"Understanding Depreciation Processing (*PeopleSoft FSCM 9.2: Asset Management*)"

(DEU) Setting Up Multi-shift Codes

To set up multi-shift codes, use the Multi-Shift Codes (MULTI_SHIFT_DEFN) component.

This topic provides an overview of multi-shift codes and lists the page used to define multi-shift codes.

Page Used to Set Up Multi-shift Codes

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Multi-Shift Codes	MULTI_SHIFT_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Depreciation, Multi-Shift Codes	Enter rates by which depreciation should be increased based on the number of production shifts that an asset is used.

Understanding Multi-shift Codes

German businesses can accelerate their depreciation by specifying usage across multiple production shifts. This increases the depreciable amount and reduces the useful life. This functionality was developed to satisfy German asset accounting rules. You can do so by establishing codes for each additional shift that indicate the rate by which annual depreciation should increase. Once you have defined these codes, you can select them for assets as they are added to the system. When you run depreciation, the Depreciation (AM_DEPR_CALC) application engine applies the rates to the depreciation calculations. As annual depreciation increases, the useful life of an asset decreases.

The following tables show the effect of multi-shift codes on depreciation amounts and useful life. In the tables, the example assumes that the asset has a cost of 1,000 EUR, a useful life of 10 years, and an in-service date of January 1, 2001. The end depreciation date is December 31, 2010. It is being depreciated by using the Straight Line method.

Example Without Multi-shift Rates

The following table shows depreciation with no multi-shift rates applied.

Year	NBV	Number of Shifts	Factor	Depreciation Amount
Year 1	1000	1	0%	100
Year 2	900	1	0%	100
Year 3	800	1	0%	100
Year 4	700	1	0%	100
Year 5	600	1	0%	100
Year 6	500	1	0%	100
Year 7	400	1	0%	100
Year 8	300	1	0%	100
Year 9	200	1	0%	100
Year 10	100	1	0%	100

Example with Multi-shift Rates

In the following multi-shift operation, the Two Shifts Factor has been established as 50 percent and the Three Shifts Factor has been established as 100 percent. Annual depreciation therefore increases, and the asset's useful life decreases from ten years to seven years:

Year	NBV	Number of Shifts	Factor	Depreciation Amount
Year 1	1000	1	0%	100
Year 2	900	1	0%	100
Year 3	800	2	50%	150
Year 4	650	2	50%	150
Year 5	500	3	100%	200
Year 6	300	3	100%	200
Year 7	100	2	50%	100

Year	NBV	Number of Shifts	Factor	Depreciation Amount
Year 8	-	-	-	-
Year 9	-	-	-	-
Year 10	-	-	-	-

Example with Multi-shift Rates by Accounting Period

The next multi-shift operation demonstrates multi-shift rates by accounting period:

Year	Period	NBV	Number of Shifts	Factor	Depreciation Before Multi-shift	Depreciation After Multi-shift	Depreciation Periods
Year 1	01-12	1000	1	0%	100	100	12
Year 2	01-12	900	1	0%	100	100	12
Year 3	01-09	800	2	50%	75	112.50	13.5
Year 3	10	687.5	3	100%	8.33	16.66	2
Year 3	11	670.84	3	100%	8.33	16.67	2
Year 3	12	654.18	3	100%	8.33	16.67	2
Year 4	01-12	637.5	2	50%	100	150	18
Year 5	01-06	487.5	2	50%	50	75	9
Year 5	07-12	412.5	1	0%	50	50	6
Year 6	01-12	362.5	3	100%	100	200	24
Year 7	01-12	162.5	2	50%	100	150	18
Year 8	01-12	12.5	1	0%	12.5	12.5	1.5
Year 9	01-12	-	-	-			-
Year 10	01-12	-	-	-			-

Note: Zero or no accounting period denotes that the whole fiscal year uses the same number of shifts. Accounting period 1 to 13 indicates multi-shift operation applies only to that specific period. If you don't set up the fiscal year or accounting period, one shift operation appears by default.

Enabling Options to Stop Negative Depreciation

This topic provides an overview of the setup necessary to stop negative depreciation and lists the pages used to enable this option.

Pages Used to Set Up the Stop Depreciation Option

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Installation Options - Asset Management	INSTALLATION_AM	Set Up Financials/Supply Chain, Install, Installation Options, Asset Management	Select the Stop Depr when NBV < Salvage check box to enable the option system-wide.
Asset Management Definition - Business Unit/Book Feature	BU_BOOK_FEATURE	Set Up Financials/Supply Chain, Business Unit Related, Assets, Asset Management Definition, Business Unit/Book Feature	Select the Stop Depr when NBV < Salvage check box to enable the option at the business unit level.
Asset Net Book Value report (AMDP2100)	RUN_AMDP2100	Asset Management, Financial Reports, Cost and Depreciation, Asset Net Book Value, Parameters	Select to report assets with negative NBV only and assets with NBV < Salvage.

Understanding the Option to Stop Negative Depreciation

In compliance with International Accounting Standards (IAS) and Generally Accepted Accounting Principles (GAAP), PeopleSoft provides the option to stop the depreciation calculation in the event the salvage value of an asset exceeds that of its NBV. Based on the rules you establish at the Installation Option and Business Unit/Book levels, the depreciation calculation program stops depreciating assets when the NBV is less than the salvage value. Hence, the system does not create negative depreciation amounts in order to reach to the salvage value at the end of the asset's useful life.

It is important to understand that the depreciation program works at the ChartField level such that you can define a particular salvage value for one ChartField value but not for the other. For example, assume that an asset belongs to two different departments (X and Y, 40% and 60%, respectively) and the total cost of the asset is 62,000 USD. However, the salvage value could be zero for department X and 2,000 USD for department Y. The depreciation calculation generates depreciation for each department separately as two independent rows.

Enable the option to stop negative depreciation for the following:

- Installation Options - Asset Management
- Asset Management Business Unit Definition - Business Unit/Book Feature page
- Asset Net Book Value Report (AMDP2100)

The Asset Net Book Value report shows multi-ChartField assets that have had their depreciation stopped for at least one ChartField. You can select to show assets with negative NBV only and you can select to show assets whose NBV is less than the salvage value.

The alternate approach to handling an asset when the NBV of an asset becomes less than its salvage value is to allow the system to generate negative depreciation until the NBV equals the salvage value at the end of the asset's useful life. To use this approach, simply do not select the Stop Depr when NBV < Salvage options.

PeopleSoft also delivers a Negative Depreciation query (AM_NEG_DEPR_NBV_LT_SALVAGE) that reports those assets that have a NBV that is less than their salvage value for any given fiscal year and period. This query is based upon the depreciation reporting table (DEPR_RPT).

See "Calculating Depreciation When Salvage Value Exceeds Net Book Value (NBV) (*PeopleSoft FSCM 9.2: Asset Management*)".

Chapter 8

Setting Up Tax Processing and Tax Reporting

Setting Up Tax Processing and Tax Reporting

This topic provides an overview of PeopleSoft Asset Management tax processing and reporting and discusses how to:

- (AUS) Define VAT thresholds.
- (AUS) Define asset unit aggregate RD.
- Define tax credits and tax credit status.
- (FRA) Define business tax by location.
- (CAN, IND, USA) Define and maintain tax classes.
- (IND) Set up tax asset blocks.
- (IND) Define tax entities and tax options.
- (JPN) Define residual rates.
- (JPN) Define owner information and return information.
- (USA) Set up retirement basis reduction codes.
- (USA) Define qualified investment codes.
- Define property tax authorities.

Understanding Tax Processing and Reporting

PeopleSoft Asset Management provides a number of tables to help you manage your tax processing and reporting needs.

- (AUS) Define value-added tax (VAT) thresholds.
- (AUS) Define asset unit aggregate RD (research and development).
- (IND) Set up asset blocks.
- (IND) Define tax entities.
- (JPN) Set up residual rate definitions.

- Set up retirement basis reduction codes.
- Set up qualified investment codes.
- Set up property tax authorities.

(AUS) Defining VAT Thresholds

Set up VAT Thresholds using the Thresholds - VAT (ASSET_THRESHOLD) component, the VAT Defaults (VAT_DFLT_SRCH_DTL) component, .

This topic provides an overview of VAT thresholds and discusses how to define VAT thresholds.

Pages Used to Define VAT Thresholds

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Thresholds - VAT	ASSET_THRESHOLD	Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Thresholds – VAT, Thresholds-VAT	Store thresholds for a number of adjustment periods.
VAT Defaults Setup	VAT_DEFAULTS_DTL	Select VAT Default link from the Asset Class definition page.	Specify VAT Defaults Setup.

Understanding VAT Thresholds

The Asset Thresholds page enables you to store thresholds for a number of adjustment periods to satisfy Australia's legislative requirements. Under Australia's "Goods and Services Tax: Division 129 - Making Adjustments For Changes In Extent Of Creditable Purpose," clients who make a form of supply known as Input Taxed Supply need to track fixed assets utilized in making this type of supply. You can track fixed assets used for Input Taxed Supply from reporting period to reporting period and make adjustments to account for any changes.

Thresholds-VAT Page

Use the Thresholds - VAT page (ASSET_THRESHOLD) to store thresholds for a number of adjustment periods.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Thresholds – VAT, Thresholds-VAT

Image: Thresholds-VAT page

This example illustrates the fields and controls on the Thresholds-VAT page. You can find definitions for the fields and controls later on this page.

Thresholds-VAT

*SetID *Schedule Type Code Currency

Description

Short Desc

Asset Thresholds Find | View All First 1 of 1 Last

*Effective Date Status

Thresholds			Personalize	Find	First	1-4 of 4	Last
	From Amount	To Amount					
1	<input type="text" value="0.01"/>	<input type="text" value="10000.00"/>			<input type="text" value="0"/>		<input type="button" value="+"/> <input type="button" value="-"/>
2	<input type="text" value="10000.01"/>	<input type="text" value="50000.00"/>			<input type="text" value="1"/>		<input type="button" value="+"/> <input type="button" value="-"/>
3	<input type="text" value="50000.01"/>	<input type="text" value="499999.99"/>			<input type="text" value="5"/>		<input type="button" value="+"/> <input type="button" value="-"/>
4	<input type="text" value="500000.00"/>	<input type="text" value="1000000000000000.00"/>			<input type="text" value="10"/>		<input type="button" value="+"/> <input type="button" value="-"/>

Enter the thresholds *from* amount and *to* amount range, as well as the number of years required for mandatory review.

Note: The system does not validate the range of thresholds that you specify. To satisfy the threshold ranges specified by the legislation, the amount ranges do not overlap.

Keep the following criteria in mind when identifying thresholds:

- The minimum threshold is 0.01.
- The From Amount, To Amount, and Number of Years fields are required for each row.
- The basis From Amount must be 0.01 more than the previous basis To Amount.
- The number of years must be greater in each subsequent row.

Note: For calculation of last date of review, if the cost of an asset is greater than the maximum to amount threshold, the number of years for the maximum to amount threshold is used.

See "(AUS) Using PeopleSoft Asset Management Options to Meet Australian Requirements (*PeopleSoft FSCM 9.2: Asset Management*)".

See [Asset Classes Page](#).

(AUS) Defining Asset Unit Aggregate RD

Set up Asset Unit Aggregate RD using the Asset Unit Aggregate RD (BU_AGG_RD) component.

Page Used to Define Asset Unit Aggregate RD

Page Name	Definition Name	Navigation	Usage
Asset Unit Aggregate RD	BU_AGG_RD	Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Asset Unit Aggregate RD – AUS, Asset Unit Aggregate RD-AUS	Calculate research and development tax deductions for R&D plant assets.

Asset Unit Aggregate RD - AUS Page


Use the Asset Unit Aggregate RD page (BU_AGG_RD) to calculate research and development tax deductions for R&D plant assets.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Asset Unit Aggregate RD – AUS, Asset Unit Aggregate RD-AUS

Image: Asset Unit Aggregate RD - AUS page

This example illustrates the fields and controls on the Asset Unit Aggregate RD - AUS page. You can find definitions for the fields and controls later on this page.



To calculate the amount of deductions that it is possible to claim, enter the aggregate R&D amount for each fiscal year. Enter the fiscal year, expenditure, and description for the business unit.

See "(AUS) Using PeopleSoft Asset Management Options to Meet Australian Requirements (PeopleSoft FSCM 9.2: Asset Management)".

See "(AUS) Using PeopleSoft Asset Management Options to Meet Australian Requirements (PeopleSoft FSCM 9.2: Asset Management)".

Defining Tax Credits

To define tax credits, use the Tax Credit (TAX_CREDITS) component and the Credit Status (TAX_CR_STATUS) component.

This topic discusses how to set up tax credits.

Pages Used to Define Tax Credits

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Tax Credits	TAX_CREDIT	Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Credits	Set up your own tax credit tables or modify existing tables.
Tax Credit Status	TAX_CR_STATUS	Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Credit Status	Set up credit statuses for tax credits by country.

Understanding Tax Credits

PeopleSoft Asset Management is delivered with tax credits defined as business incentive credits:

- Energy Tax Credit
- Regular Investment Tax Credit
- Rehabilitation Tax Credit

These credits are based on existing U.S. tax law, and it is recommended that you review the delivered Tax Credit table before adding any credits.

Credits Page

Use the Credits page (TAX_CREDIT) to set up your own tax credit tables or modify existing tables.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Credits

Image: Credits page

This example illustrates the fields and controls on the Credits page. You can find definitions for the fields and controls later on this page.

Credits				
SetID	SHARE	Country	USA USA	
Tax Credit Type	E			
Tax Credit Code	S			
Description	Solar Energy			
Tax Credit Information				
Reduction Type	*Effective Date	Status	Tax Credit	Basis Reduction Rate Percent
N	01/01/1988	Active	10.000000	0.000000

Reduction Type

Indicates whether a reduction in the cost basis is required. Three codes are provided:

B: Basis reduction

P: Percentage rate reduction

N: No reduction

Tax Credit

Enter the tax credit amount.

Basis Reduction Rate Percent

Enter the corresponding rate to reduce the basis. A basis reduction rate of 100 percent means that there will be no reduction in the cost basis of the asset to which the tax credit rate is applied.

(FRA) Defining Business Tax by Location

Use the Business Tax by Location (ASSET_LOC_RATE) component to define business tax by location.

PeopleSoft Asset Management enables you to store tax rates by location. These tax rates are used to calculate and report business tax assessed on the gross value of fixed assets. This taxation method is used in global settings, especially France.

Page Used to Define Business Tax by Location

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Asset Loc Rate	ASSET_LOC_RATE	Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Business Tax by Location, Asset Loc Rate	Enter and store tax rates by location. Rates are used to calculate and report a business tax assessed on the gross value of fixed assets in some countries, especially France.

Related Links

"(FRA) Using PeopleSoft Asset Management Options to Meet French Requirements (*PeopleSoft FSCM 9.2: Asset Management*)"

(CAN, IND, and USA) Defining and Maintaining Tax Classes

Use the Tax Class Definition (TAX_CLASS_DEFN) component to set up tax classes.

This topic provides an overview of how to use tax classes and discusses how to define tax classes.

Page Used to Define Tax Class

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Tax Class	TAX_CLASS_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Classes	<p>Set up or review tax classes. Tax Class determines the period over which you expense tax depreciation.</p> <p>The Tax Class table for the SHARE tableset is shipped with guideline class lives for property. Tax Class is informational only and is not used in any calculations.</p> <p>You can set up your own tax classes or use those already set up in the SHARE Tax Class table. Define class and block rate for the tax class.</p> <p>This is equivalent to the <i>tax group</i> for India.</p>

Understanding How to Use Tax Classes

Tax class is a classification system established by the U.S. Internal Revenue Service (IRS) to determine the period over which you can expense tax depreciation. The IRS has assigned classes to particular types of depreciable property, and there are assigned rates for each class. The classifications delivered with PeopleSoft Asset Management list the available IRS-defined tax classes.

Tax class rates are used in Canada to calculate depreciation as allowed by the Capital Cost Allowance (CCA). Asset pools or classes and CCA rates are set by governmental regulations. In the year that assets are acquired, 50 percent of the normal rate should be used. The value that you enter for an asset tax class for the CCA rate percent is used later when you run a process to calculate the CCA rate.

Tax class is also used to define tax rates by group for processing tax and depreciation in India. The tax group is a subcategory of the tax block in India. PeopleSoft Asset Management defines tax blocks in the Asset Block component. Therefore, tax class is a subgroup of the asset block in PeopleSoft Asset Management. The tax class is associated with assets in the Profile component and the Express Add component as Guideline Class.

Related Links

"(CAN) Using Asset Management Options to Meet Canadian Requirements (*PeopleSoft FSCM 9.2: Asset Management*)"

"(IND) Using PeopleSoft Asset Management Options to Meet Indian Requirements (*PeopleSoft FSCM 9.2: Asset Management*)"

Classes Page

Use the Classes page (TAX_CLASS_DEFN) to set up or review tax classes.

Tax Class determines the period over which you expense tax depreciation. The Tax Class table for the SHARE tableset is shipped with guideline class lives for property. Tax Class is informational only and is not used in any calculations. You can set up your own tax classes or use those already set up in the SHARE Tax Class table. Define class and block rate for the tax class. This is equivalent to the tax group for India.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Classes

Image: Classes page

This example illustrates the fields and controls on the Classes page. You can find definitions for the fields and controls later on this page.

Classes

SetID SHARE Guideline Tax Class 00.11

Tax Class Definition Find | View All First 1 of 1 Last

*Effective Date 01/01/1900 *Status Active

Description Office Furniture, Fixtures, and Equipment

Class Life Range

Lower 8.0

Middle 10.0

Upper 12.0

Class/Block Rate

Asset Block

Rate%

Comments

Includes furniture and fixtures that are not a structural component of a building. Includes such assets as desks, files, safes, and communications equipment. Does not include communications equipment that is included in other classes.

Class Life Range

Lower

Enter the asset lifetime expectancy minimum in a range.

Middle

Enter the asset lifetime expectancy average or middle or range.

Upper

Enter the asset lifetime expectancy maximum in a range.

Class/Block Rate

Asset Block

Enter the asset block with which this tax class should be associated for depreciation and tax reporting in India. Asset tax blocks are defined by the Indian Tax Depreciation Act (Indian Income Tax Act 1961).

Rate % (rate percentage)

(CAN) Canada: Enter the appropriate CCA rate percentage for this tax class to calculate the CCA for Canada.

The Capital Cost Allowance (CCA) is "a tax deduction that Canadian tax laws allow a business to claim for the loss in value of capital assets due to wear and tear or obsolescence" (Canada Customs and Revenue Agency). If you buy a property or a piece of equipment to use in your business, you don't deduct the entire cost of it against your income for that particular year. Instead, you deduct a calculated portion of the expense over a period of years as the property or the equipment depreciates. The Canada Customs and Revenue Agency has assigned classes to particular types of depreciable property, and there are assigned rates for each class.

(IND) India: Enter the tax group rate percentage that will be associated with the asset block and tax entity used to process depreciation and tax reporting for India.

Related Links

"(CAN) Using Asset Management Options to Meet Canadian Requirements (*PeopleSoft FSCM 9.2: Asset Management*)"

"Understanding PeopleSoft Asset Management in Global Settings (*PeopleSoft FSCM 9.2: Asset Management*)"

(IND) Setting Up Tax Asset Blocks

Use the Asset Block (ASSET_BLOCK) component to define asset blocks.

This topic provides an overview of asset blocks and discusses how to define asset blocks.

Page Used to Set Up Asset Blocks

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Asset Block	ASSET_BLOCK	Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Asset Block, Asset Block	Define assets blocks. This is equivalent to the <i>tax block</i> for India.

Understanding Asset Blocks

Asset blocks are required for India tax reporting. According to the Indian Tax Depreciation Act (Indian Income Tax Act 1961), does not recognize depreciation on individual assets. Instead, it groups similar pools of assets under the concept of a *tax block*. There are only four blocks of assets prescribed under the act:

- Buildings.
- Furniture and fixtures.
- Machinery and plants.

- Intangibles.

Annual tax depreciation is reported to the India tax authority per tax block, per fiscal year. The PeopleSoft system uses the asset block to maintain tax block definitions for India.

Asset Block Page

Use the Asset Block page (ASSET_BLOCK) to define assets blocks.

This is equivalent to the tax block for India.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Asset Block, Asset Block

Image: Asset Block Page

This example illustrates the fields and controls on the Asset Block Page. You can find definitions for the fields and controls later on this page.

Asset Block		
SetID SHARE		
Block Details		
		Personalize Find First 1-5 of 5 Last
*Block of Assets	Description	Comment
1 BUILDINGS	Buildings	
2 FURNITURE & FIXTURES	Furniture & Fixtures	
3 PLANTS & MACHINERY	Plants & Machinery	
4 INTANGIBLES	Intangibles	

Related Links

"(IND) Using PeopleSoft Asset Management Options to Meet Indian Requirements (*PeopleSoft FSCM 9.2: Asset Management*)"

(IND) Defining Tax Entities and Tax Options

Use the Tax Entity Definition (TAX_ENTITY_DEFN) component to define tax entities and tax options.

This topic discusses how to:

- Set up tax entities for Indian tax reporting.
- Set up tax options.

The tax entity is the reporting entity for depreciation and taxes in India. It is defined by the asset blocks, tax class tax rates, SetID calendar, and business unit and books that are associated with it.

Pages Used to Define Tax Entities and Tax Options

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Entity	TAX_ENTITY_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Tax Entity Definition, Entity	Define the tax reporting entity. Tax entity is composed of one or more business units, and tax reporting is required per entity for India.
Tax Options	TAX_ENTITY_ATTR	Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Tax Entity Definition, Tax Options	Define the 50 percent rule as it applies for assets. Assets in India are grouped separately to include assets that have been in service for more than 180 days in one group and those that have been in service for less than 180 days in another. For assets in service less than 180 days, only 50 percent of normal depreciation rate is allowed (per Section 32).

Entity Page

Use the Entity page (TAX_ENTITY_DEFN) to define the tax reporting entity.

Tax entity is composed of one or more business units, and tax reporting is required per entity for India.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Tax Entity Definition, Entity

Image: Entity page

This example illustrates the fields and controls on the Entity page. You can find definitions for the fields and controls later on this page.

Tax/Reporting Entity INDIA
Description: India Tax/Reporting Entity

Entity Book Information Find First 1-2 of 2 Last

*Entity Book: CORP *Calendar SetID: SHARE *Calendar ID: I1

Book	*Business Unit	*Book Name	Calendar	Currency	Conversion Date		
1	IND01	CORP	I1	INR	01/01/2000	31	+ -
2	IND02	CORP	I1	INR	01/01/2000	31	+ -
3	IND03	CORP	I1	INR	01/01/2000	31	+ -

*Entity Book: TAX *Calendar SetID: SHARE *Calendar ID: I1

Book	*Business Unit	*Book Name	Calendar	Currency	Conversion Date		
1	IND01	TAX	I1	INR	01/01/2000	31	+ -
2	IND02	TAX	I1	INR	01/01/2000	31	+ -
3	IND03	TAX	I1	INR	01/01/2000	31	+ -

Tax/Reporting Entity

Displays the name of the tax reporting entity that you are defining or working with.

Entity Book

The value selected here defines how to group the tax or reporting entity. All asset books are available regardless of SetID.

Calendar SetID

Select the SetID for the calendar that you want to associate with this entity book. Once a calendar SetID is selected, you are limited to the calendar IDs available within that SetID.

Calendar ID	Select the calendar ID from the available calendars for the selected SetID.
Business Unit	Enter the business unit to be included in this tax reporting entity from the list of available business units.
Book Name	Enter the asset book name (business unit or book) to be included in this tax reporting entity from the list of available business unit or book definitions.
Calendar	Displays the calendar code.
Currency	Displays the currency code based on the value associated with the book entered.
Conversion Date	The conversion date is equal to the actual date or fiscal year start date of the beginning of asset management operations in India. This determines whether you can modify the opening balance calculated in the first fiscal year. This is used only for tax report entity and not just reporting entity.

Tax Options Page

Use the Tax Options page (TAX_ENTITY_ATTR) to define the 50 percent rule as it applies for assets.


Assets in India are grouped separately to include assets that have been in service for more than 180 days in one group and those that have been in service for less than 180 days in another. For assets in service less than 180 days, only 50 percent of normal depreciation rate is allowed (per Section 32).

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Tax Entity Definition, Tax Options

Image: Tax Options page

This example illustrates the fields and controls on the Tax Options page. You can find definitions for the fields and controls later on this page.



This page defines whether to use the Indian 50 percent rule. Assets owned for less than the specified number of days are depreciated at half of the normal rate, or 50 percent. It also defines whether manual adjustments to the tax depreciation balance inquiry (TAX_DEPR_BAL) page are allowed.

50% rule, assets in service <	Enter the maximum number of in-service days to which the 50 percent rule applies. For example, if the 50 percent rule applies for assets in service <i>less than</i> 180 days, enter <i>180</i> .
Country	Select the country for which the 50 percent rule applies.
Update on Close Balances	Select one of these options: Update on Close Balances: Select this option if the calculated closing balance can be manually adjusted. Update on other amounts: Select this option if other calculated amounts can be manually adjusted.

Related Links

"(IND) Using PeopleSoft Asset Management Options to Meet Indian Requirements (*PeopleSoft FSCM 9.2: Asset Management*)"

(JPN) Defining Owner Information and Return Information

Use the Owner Information (OWNER_INFO_DEFN) and the Return Information (RETURN_INFO_DEFN1) components to enter information used in the Tax Roll report.

This topic lists the pages used to enter information for the Tax Roll report.

This feature is used in Japanese tax reporting.

Pages Used to Enter Tax Roll Report Information

Page Name	Definition Name	Navigation	Usage
Owner Information	OWNER_INFO_DEFN	Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Owner Information Defn. - JPN, Owner Information	Enter owner information that is printed on the Depreciable Asset Tax Return (Tax Roll) report.
Return Information	RETURN_INFO_DEFN1	Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Return Information Defn. - JPN, Return Information	Enter information that is required for the Depreciable Asset Tax Return (Tax Roll) report.

Entering Japanese Tax Information

See "(JPN) Using PeopleSoft Asset Management Options to Meet Japanese Requirements (*PeopleSoft FSCM 9.2: Asset Management*)".

Setting Up Retirement Basis Reduction Codes

To set up retirement basis codes, use the Retirement Basis Reduction (TRAN_EXCLUDE_TBL) component.

This topic discusses how to define retirement basis codes.

Page Used to Set Up Retirement Basis Codes

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Retirement Basis Reduction	TRAN_EXCLUDE_TBL	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Retirement Basis Reduction	Set up retirement basis reduction codes.

Retirement Basis Reduction Page

Use the Retirement Basis Reduction page (TRAN_EXCLUDE_TBL) to set up retirement basis reduction codes.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Retirement Basis Reduction

These codes are used when you opt to retire an asset by using its original cost basis adjusted by all non-excluded transactions. In this way, for example, you could exclude any indexed revaluation adjustments.

Note: For this option to work correctly, any transaction type or types that you want to exclude must have unique transaction codes.

(USA) Defining Qualified Investment Codes

To set up qualified investment codes, use the Qualified Investment Codes (QIV) component.

This topic provides an overview of qualified investment codes and lists the page used to define qualified investment codes.

Page Used to Define Qualified Investment Codes

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Qualified Investment	QUAL_INV	Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Qualified Investments, Qualified Investments	Add or modify qualified investment codes. Enter a unique ID to add a new code. Define the life expressed as periods in Compare Life. The life entered here is validated against the asset's useful life.

Understanding Qualified Investment Codes

When one or more tax credits are taken for an asset, you may need to adjust the basis of that asset before additional credits can be computed. PeopleSoft Asset Management uses the Qualified Investment Codes to determine the portion of the asset's basis that qualifies for the tax credit. Eligibility for each code is determined by the effective date compared to the placed-in-service date for the asset. In addition to tax credits, standard Qualified Investment Codes corresponding to a specific tax system and life are included with the delivered tableset.

Defining Property Tax Authorities

Use the Tax Authority (AM_TAX_AUTHORITY) component to define the property taxing authority codes.

Property tax is administered differently based on the governing laws based on the taxing structure of the location of the property.

Page Used to Define Property Tax Authority Codes

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Tax Authority	AM_TAX_AUTHORITY	Set Up Financials/Supply Chain, Product Related, Asset Management, Taxes, Property Tax Authorities, Tax Authorities	Define codes for property tax authorities to be used to associate with taxable property assets.

Integrating PeopleSoft Asset Management with Other Products

Integrating PeopleSoft Asset Management with Other Products

This topic provides an overview of how Asset Management integrates with other applications and discusses how to:

- Integrate with PeopleSoft Billing.
- Integrate with PeopleSoft Budgeting.
- Integrate with PeopleSoft General Ledger.
- Integrate with PeopleSoft IT Asset Management.
- Integrate with PeopleSoft Maintenance Management.
- Process PeopleSoft Asset Management, Purchasing, and Payables transactions.
- Process PeopleSoft Purchasing and Payables transactions with PeopleSoft Asset Management.
- Integrate with PeopleSoft Project Costing.
- Integrate with PeopleSoft Real Estate Management.
- Integrate with PeopleSoft Strategic Sourcing.
- Preview data in the loader tables.
- Approve load lines.
- Run the transaction loader.
- Consolidate and unitize assets.
- Export property tax data to third-party tax systems.
- Import asset data by using the Excel to Component Interface utility.

Understanding How PeopleSoft Asset Management Integrates with Other Applications

PeopleSoft Asset Management directly integrates with the following PeopleSoft applications:

- Billing

- Budgeting
- General Ledger
- IT Asset Management
- Maintenance Management
- Payables
- Project Costing
- Purchasing
- Real Estate Management
- Strategic Sourcing

Integrating with PeopleSoft Billing

PeopleSoft Asset Management integrates with PeopleSoft Billing to pass transactions from AM when the *Retire With Sale* option has been exercised for an asset. When this option is enabled, you can generate a bill to the purchaser of an asset that is being moved out of your asset database, and pass the transaction to PeopleSoft Billing. PeopleSoft Billing then generates appropriate accounting entries to relieve fixed assets, calculate value-added tax (VAT) as necessary, debit PeopleSoft Receivables, and post to PeopleSoft General Ledger.

Integrating with PeopleSoft Budgeting

PeopleSoft Asset Management provides an interface to PeopleSoft Budgeting. To create asset-based budgets, make asset data and depreciation information available to PeopleSoft Budgeting.

Asset Management uses an SQR (Structured Query Report) process (AMBD1000.SQR) to populate the budget asset (BD_ASSET*) tables. Once you run the SQR process to populate the asset tables in Budgeting, you can use asset data in Budgeting. Load all assets from a business unit for a specified fiscal year or period range directly into the Budgeting tables to integrate asset information with Budgeting.

Capital acquisition plans (CAPs) can be added directly into PeopleSoft Asset Management.

Integrating with PeopleSoft General Ledger

PeopleSoft Financials requires that you transfer journals from PeopleSoft Asset Management to your general ledger system. This may be PeopleSoft General Ledger or another external system. As part of the setup for PeopleSoft Asset Management, coordinate with PeopleSoft General Ledger to make sure there is a general ledger business unit and ledger, general ledger calendar, journal sources, and accounting entry templates. When you define operators, set up journal distribution privileges for them. This setup enables you to distribute accounting entries for asset transactions and depreciation and to generate journals to PeopleSoft General Ledger.

If the general ledger and asset management databases are not integrated, or if you use a different general ledger system, you must complete some prerequisite tasks before integrating the two systems.

Integrating with PeopleSoft IT Asset Management

PeopleSoft IT Asset Management is a system of integrated management processes, strategies, and technologies that provide you with complete control over your IT assets throughout the asset life cycle. PeopleSoft Asset Management integrates with PeopleSoft IT Asset Management by sharing assets in the Asset Repository. PeopleSoft IT Asset Management embeds network discovery tools into PeopleSoft Asset Management to collect perpetual IT asset inventory for reconciliation to the Asset Repository Manager (ARM). When you use PeopleSoft IT Asset Management with PeopleSoft Maintenance Management, the repository stores organizational asset information including physical and financial definitions, acquisition history, and maintenance history. PeopleSoft IT Asset Management provides a central workspace to manage discovered and reconciled results, monitor collected metrics, and drill down to detailed asset data for problem solving and information gathering activities. This interactive workspace collects detailed hardware and software inventory information and authorized versus unauthorized license deployment with access to contract and warranty information relative to IT assets. Oracle has partnered with a provider of network discovery tools in PeopleSoft IT Asset Management to perpetually inventory IT assets, including software and hardware devices that connect to your network. After the discovery tool collects usage data, it is reconciled to the Asset Repository Manager by means of configurable business rules that define reconciling data-points. The asset reconciliation engine compares discovered asset inventory to that stored in the ARM, where all organizational assets are stored with complete business data, acquisition history, maintenance history, and financial data. Because IT assets are perpetually inventoried by means of network discovery tools, IT assets are always accurately reflected in business data and financial reporting.

Integrating with PeopleSoft Maintenance Management

The asset repository facilitates sharing common asset data regardless of the preferred view and level of granularity. Maintenance management requires a technical view of an asset to maintain appropriate spare parts lists and to facilitate maintenance scheduling of service, materials, and labor. PeopleSoft Maintenance Management builds maintenance functionality off of asset management software utilities such as auto-discovery, software delivery, license tracking, usage meter monitoring, configuration management, and contract management. Each component can be identified by serial number, model, manufacturer, and associated warranty, and the Asset Repository carries original cost per component when known.

Integrating with PeopleSoft Payables - Capitalizing Assets upon Receipt of Invoice

When you use PeopleSoft Asset Management with PeopleSoft Payables, you can share asset information between these applications. Before you can send voucher information to PeopleSoft Asset Management, you must determine that the point in the payment process at which you want to capitalize the asset is when the invoice for the asset is received and registered in Payables.

If your PeopleSoft Financials and Supply Chain suite includes Payables and Asset Management, you have real-time access to the supplier, voucher, and order data in that system. The interface between these PeopleSoft applications eliminates the need for dual maintenance of vouchers and their corresponding asset data. Payables sends all asset additions, adjustments, and retirements for unposted vouchers to PeopleSoft Asset Management. PeopleSoft Asset Management receives information from PeopleSoft Payables in a consistent manner by using Application Engine programs.

The PeopleSoft system enables *split-funding* of assets within the business processes for PeopleSoft Payables. A one-time setup of the batch processes used by PeopleSoft Asset Management to "receive" assets from PeopleSoft Payables allows a single asset ID to be assigned to multiple cost or expense

distributions of a single asset. The asset capitalization and depreciation amounts can be allocated to one or many distribution lines using a sequence number as a subidentifier.

Integrating with PeopleSoft Payables - Sending Lease Payments to Payables

The integration between PeopleSoft Asset Management lease payments and PeopleSoft Payables automatically generates vouchers for lease payments that are calculated in Asset Management. This includes both capital and operating leases. Additionally, the lease payment schedule segregates the principal and interest of each payment and is used by the Depreciation Close process (AMDPCLOS) to generate the payment accounting entries. The lease payments are allocated on a monthly basis in accordance with GAAP. Asset Management generates the associated monthly accrual accounting entries. Lease Interest Contra and Lease Obligation Contra accounts must be established as clearing accounts, which are offset by the Payables voucher entries. This integration is enabled at the Asset Management business unit level.

See "Entering Regular Vouchers (*PeopleSoft FSCM 9.2: Payables*)".

Integrating with PeopleSoft Project Costing

PeopleSoft Asset Management integrates with PeopleSoft Project Costing by sharing information about assets associated with ongoing projects. Assets that originate in Project Costing are usually the outcome of construction projects.

When performing asset maintenance, organizations frequently do so by using a project effort. By creating a project, the maintenance organization is oftentimes able to more precisely plan and budget, track, manage, and account for the effort than if numerous unrelated work orders were generated. The Manage Project feature uses the Maintain Asset via Project process primarily by introducing the concept of the work order into the process and adds the process of project-based management of asset maintenance. Maintaining an asset with a project involves creating and planning a project, incurring costs against the project, and expensing or capitalizing costs from the work. An enterprise that must both perform its own capital improvement projects and manage large-scale ad hoc maintenance and preventive maintenance efforts may use projects to manage asset maintenance activities.

The *Maintain Asset via Project* process manages the high-level steps of undertaking a project to maintain or upgrade an asset. The typical process is:

- Plan and budget for maintenance of an asset.
- Obtain approval for the maintenance.
- Create a project plan and work orders for the effort to maintain the asset.
- Fulfill the work orders.
- Capture the costs—labor, materials, and depreciation—associated with the effort.
- Identify rules by which capitalization of capital improvement costs will occur.
- Determine whether to expense or capitalize various project costs.
- Capitalize and expense project costs.

PeopleSoft Project Costing provides the *Create and Plan Project to Maintain an Asset* process. The goal is to establish a project and associated activities that enable the organization to begin work on maintaining an asset. Once the project and activities are created, work orders are issued to authorize maintenance tasks

to occur. Normally, the project is created for either capital improvement projects in which the costs will be capitalized or for large-scale maintenance projects that require more sophisticated project management than the simple dispatching of technicians to work orders.

The process to account for project and asset costs enables the operations manager to review transactions booked to the project for accuracy, and for the accountant responsible for projects and assets to examine the costs to be sure that they contain the correct ChartField values for expenses and the correct information to affect asset values.

Integrating with PeopleSoft Purchasing

When you use PeopleSoft Asset Management with PeopleSoft Purchasing, you can share asset information between these applications. Before you can send receipt information to PeopleSoft Asset Management, you must determine that the point in the procurement process at which you want to capitalize the asset is when an asset is received in PeopleSoft Purchasing.

If your PeopleSoft Financials and Supply Chain suite includes PeopleSoft Purchasing as well as PeopleSoft Asset Management, you have real-time access to the supplier, voucher, and order data in this system. The interface between these PeopleSoft applications eliminates the need for dual maintenance of receipts and their corresponding asset data. PeopleSoft Purchasing sends all asset additions, adjustments, and retirements for unposted receipts to PeopleSoft Asset Management. PeopleSoft Asset Management receives information from PeopleSoft Purchasing in a consistent manner by using Application Engine programs.

The PeopleSoft system enables *split-funding* of assets within the business processes for Purchasing. A one-time setup of the batch processes used by PeopleSoft Asset Management to "receive" assets from Purchasing allows a single asset ID to be assigned to multiple cost or expense distributions of a single asset. Using a sequence number as a subidentifier, the asset capitalization and depreciation amounts can be allocated to one or many distribution lines.

Integrating with PeopleSoft Real Estate Management

PeopleSoft Asset Management enables you to manage property assets and to maintain property-specific details such as legal descriptions and property tax information within the Asset Repository. Centralizing this asset data in one database enables multiple applications to access the asset and exchange data details as needed. When setting up assets, you can specify property information, space statistics, and location information. You can break property assets down into sublevels: Site, Building, Area, Floor, and Space. Properties can be created directly within Asset Management, then optionally fed to a computer-aided facility management (CAFM) utility, exploded into working facility maps where assignments of space allocation and employees can be made, and then fed back to update the repository.

The property component enables you to manage property tax bill tracking and other statistics that help with reporting and portals such as occupancy, maximum occupancy, square footage per department or other categorization, and so on.

Leases can be attached at any asset level but once they are, their children cannot be attached while that lease is still active. Subleases allow them to be released out, and that is the only case in which the rule does not apply. Total area is supplied by default and is controlled by the repository, but rentable and usable space can be modified on the lease. With PeopleSoft Real Estate Management, you can create and manage a lease between a landlord and tenant simply by pulling the property asset data stored within the Asset Repository.

Integrating with PeopleSoft Strategic Sourcing

PeopleSoft Asset Management integrates with the PeopleSoft Supply Chain Management Strategic Sourcing module, enabling you to put unused assets up for auction and, if a bid is awarded, automatically generate a retirement transaction.

Integrating with PeopleSoft Billing

This section provides an overview of how to integrate PeopleSoft Asset Management with PeopleSoft Billing and discusses how to enable the integration.


Understanding How to Integrate with PeopleSoft Billing

PeopleSoft Asset Management integration with PeopleSoft Billing enables you to complete asset lifecycle processes, bill retire with sale transactions, and generate accounting entries in PeopleSoft Billing and PeopleSoft Asset Management. Using the AM/BI Interface process, you can pass asset *Retire With Sale* transactions from PeopleSoft Asset Management to PeopleSoft Billing to generate appropriate accounting entries to relieve fixed assets, calculate VAT as necessary, debit Receivables, and post to PeopleSoft General Ledger. You can also send asset reinstatements to PeopleSoft Billing as credit lines.

This diagram displays the data and process flow that occurs when you integrate PeopleSoft Asset Management with PeopleSoft Billing:

Image: PeopleSoft Asset Management integration with PeopleSoft Billing process data flow

Data and process flow for integration between PeopleSoft Asset Management and PeopleSoft Billing:



When an asset is retired by sale in PeopleSoft Asset Management:

1. Retire the asset with a sale in PeopleSoft Asset Management and collect the appropriate customer information within PeopleSoft Asset Management.
2. Send the transaction information and billing information to the Billing Interface using the AM/BI process (AM_BI_INTFC).

When PeopleSoft Strategic Sourcing puts an asset on an auction site for sale:

1. If the auction bid is awarded, PeopleSoft Strategic Sourcing sends the customer information and asset sold proceeds to PeopleSoft Asset Management to initiate and complete the retirement transaction with proceeds from bid price.
 - a. PeopleSoft Asset Management retires the asset and creates the appropriate accounting entries for sale.
 - b. You run the AM BI Interface process to send the retirement sales transaction and billing information to Billing.

Note: You must collect customer information at the time of sale and send this information to PeopleSoft Billing with the retirement transactions, because assets can be purchased by an individual or entity not currently in the Customer Master table.

2. If the auction bid is not awarded, PeopleSoft Strategic Sourcing returns the asset to PeopleSoft Asset Management and changes the auction status to enable PeopleSoft Asset Management to realize any asset activity as a cost adjustment, transfer, or retirement.

PeopleSoft Asset Management interfaces with PeopleSoft Billing if you installed PeopleSoft Billing and if you:

1. Select the Billing Interface Processing option on the Asset Management Interface Options page, and set up a default billing business unit, bill type, bill source, and bill by identifier.
2. Select the Create Bill option on the Retire Assets page.

If PeopleSoft Asset Management interfaces with PeopleSoft Billing, PeopleSoft Asset Management sends the proceeds to the billing clearing account. PeopleSoft Asset Management sends to PeopleSoft Billing the proceeds clearing account to reflect both sides of the customer's debt. When PeopleSoft Billing receives the PeopleSoft Asset Management data, PeopleSoft Billing reverses the clearing account and generates the receivable account.

PeopleSoft Asset Management calculates an estimated VAT amount (if necessary), generates retirement and sales accounting entries, and posts the entries to PeopleSoft General Ledger. If PeopleSoft Asset Management interfaces with PeopleSoft Billing, you run the AM/BI Interface process to send the transactions to Billing to book the sale, create accounting entries, generate the invoice, and post the debt to PeopleSoft Receivables. If retirement is originated from PeopleSoft Strategic Sourcing, Asset Management does not send VAT information to Billing (Strategic Sourcing does not process VAT). If retirement is originated from Assets Management, Asset Management calculates VAT estimates only.

Note: PeopleSoft Asset Management VAT is *estimated*, and PeopleSoft Billing VAT is the actual *calculated* VAT taking customer and bill-by information into account.

If a country allows the Domestic Reverse Charge VAT treatment and the corresponding VAT Asset Class and Customer are set to 'Domestic Reverse Charge, the Domestic Reverse Charge Sales Code will be carried to PeopleSoft Billing along with the calculated Domestic Reverse Customer Amount.

See "Understanding VAT (*PeopleSoft FSCM 9.2: Global Options and Reports*)".

Enabling PeopleSoft Billing Integration with PeopleSoft Asset Management

To establish processing between PeopleSoft Asset Management and PeopleSoft Billing, you must select the Billing Interface Processing option from the Billing Interface group box on the AM Business Unit Definition page. This activates integration between the two applications and enables the Create Bill option on the Asset Management Retirement page. PeopleSoft Billing is the only billing interface that is supported by this feature.

When you activate the Billing interface, you must also enter values for the BI Unit, Bill Source, Bill Type, and Bill By Identifier fields. If Billing business units and other Billing information to complete the business unit definitions on this page have not yet been defined, you must do so before beginning transaction processing.

You must define the default book in the AM Business Unit Definition component. This is the default book for the AM/BI Interface. This should also be established as the primary book in your PeopleSoft General Ledger setup.

Also, establish the accounting entry template to be used in retirement transactions in which the asset is retired with the disposal code *Retire w/Sale*. You must designate the account for the Billing clearing account, *Proceeds to Billing*, in the accounting entry template. This maintains balanced accounting entries between PeopleSoft Asset Management and PeopleSoft Billing accounts.

PeopleSoft Asset Management and PeopleSoft Billing Business Unit Mapping

To accommodate interunit and noninterunit scenarios for PeopleSoft Asset Management asset retirement integration, the AM BI Interface process writes the BUSINESS_UNIT_AM and BUSINESS_UNIT_AMTO values to the INTFC_BI table, writes the BUSINESS_UNIT_AM value to the BI_HDR table, and writes the BUSINESS_UNIT_AMTO value to BI_LINE table. Writing these values to Billing tables enables you to track the entity retiring the assets, as well as the entity receiving the asset. Billing supports one General Ledger To business unit (BUSINESS_UNIT_TO) per invoice. Therefore, PeopleSoft Asset Management To business units must share the same corresponding PeopleSoft General Ledger business unit. Billing supports multiple Asset Management To business units at the line level, but each business unit to must be booked to the same General Ledger To business unit.

PeopleSoft Asset Management is not required to populate the INTFC_BI.INTERUNIT_FLG. If PeopleSoft Asset Management passes an interunit customer, the PeopleSoft Billing Interface populates this field with *Y* (yes).

The Billing Interface also populates the INTFC_BI.BUSINESS_UNIT_GL field, based on the billing business unit (INTFC_BI.business_unit) that Asset Management passes.

If the Billing Interface is creating an interunit bill (INTFC_BI.InterUnit_flg = *Y*), it populates the INTFC_BI.BUSINESS_UNIT_TO field (when Asset Management passes no value) with the BUSINESS_UNIT_GL value, which the interface obtains from the CUST_OPTION table, based on the customer ID. If the Billing Interface is not able to determine a value for the INTFC_BI.BUSINESS_UNIT_TO field using customer defaulting, it stops the transaction and marks it in error.

Related Links

[Interface Options Page](#)

[Defining Accounting Entries](#)

"Understanding PeopleSoft Billing Business Units (*PeopleSoft FSCM 9.2: Billing*)"

"Defining Bill Types (*PeopleSoft FSCM 9.2: Billing*)"
 "Defining Bill Sources (*PeopleSoft FSCM 9.2: Billing*)"
 "Bill-by Identifier Page (*PeopleSoft FSCM 9.2: Billing*)"

Integrating with Budgeting

This topic provides an overview of how to integrate PeopleSoft Asset Management with PeopleSoft Budgeting and discusses how to use the Budgets Interface page.

Pages Used to Integrate with Budgeting

Page Name	Definition Name	Navigation	Usage
Load Asset Catalog	BD_RUN_AM_ITEM	Asset Management, Asset Transactions, Capital Acquisition Planning, Load Budgeting Asset Catalog	Load the budgeting asset catalog.
Run Budgets to AM Interface	RUN_AMBD1000	Asset Management, Asset Transactions, Capital Acquisition Planning, Send To Budgeting	Load all assets from a business unit for a fiscal year or period range that you specify directly into the Budgets tables.

Understanding How to Integrate with Budgeting

Asset Management provides an interface to Budgeting. To create asset-based budgets, make asset data and depreciation information available to Budgeting. The Asset Management to Budgeting Structured Query Report (SQR) populates the BD_ASSET* tables. Once you run the SQR (AMBD1000.SQR) to populate the asset tables in Budgeting, you can use asset data in Budgeting.

CAPs can be added directly to Asset Management.

Load all assets from a business unit for a specified fiscal year or period range directly into the Budgeting tables to integrate asset information with Budgeting.

Using the Budgets Interface

Use the Run Budgets to AM Interface page (RUN_AMBD1000) to load all assets from a business unit for a fiscal year or period range that you specify directly into the Budgets tables.

Navigation

Asset Management, Asset Transactions, Capital Acquisition Planning, Send To Budgeting

The interface tables loaded by this process are emptied and reloaded each time that it is run. A separate Budgets process, AMBD1000.SQR, formats the asset data for use in the Budgeting process.

Note: If the number of assets that you are processing is large (200,000 or more), consider reducing it to smaller batches. For example, you might process one or more departments, categories, projects, or a similar breakdown to narrow the number of items being processed at one time. The exact number of assets that make up the "breaking point" beyond which you should process in smaller batches varies depending on your database platform, tablespace and rollback size, and other factors.

Integrating with General Ledger

This topic provides an overview of how to integrate PeopleSoft Asset Management with PeopleSoft General Ledger.

Understanding How to Integrate with General Ledger

Regardless of the general ledger system that you use, you must transfer journals from Asset Management to General Ledger. As part of the setup for your asset system, establish a general ledger business unit and ledger, general ledger calendar, journal sources, and accounting entry templates. When you define operators, set up journal distribution privileges for them. This setup enables you to distribute accounting entries for asset transactions and depreciation and to generate journals to General Ledger.

If the General Ledger and Asset Management databases aren't integrated, or if you use a different general ledger system, you need to complete some prerequisite tasks before integrating the two systems.

Two processes are required to complete the bridge between Asset Management and another general ledger system:

- At installation, rename JRNL_HEADER to JRNL_HEADER_FS, and rename JRNL_LN to JRNL_LN_FS.

Using Application Designer, change these records from views to SQL tables, and create the tables.

- On a regular basis, unload the journal headers and lines from one database to the other.

To send journals to an outside general ledger system, design a conversion program that converts Asset Management journal headers and lines to the format required by your general ledger system.

PeopleSoft Asset Management also uses the book code and document sequencing functionality available through PeopleSoft General Ledger.

Related Links

"Integrating General Ledger with Other PeopleSoft Applications (*PeopleSoft FSCM 9.2: General Ledger*)"

[Defining Document Sequencing](#)

[Defining Accounting Entries](#)

Integrating Asset Management with IT Asset Management

This topic provides an overview of how to integrate PeopleSoft asset management with PeopleSoft IT Asset Management.

Understanding How to Integrate with IT Asset Management

IT Asset Management represents an entire system of integrated management processes, strategies, and technologies implemented to provide you with complete control over your IT assets throughout the asset life cycle. Asset Management integrates with IT Asset Management by sharing assets in the Asset Repository.


IT Asset Management embeds network discovery tools into Asset Management to collect perpetual IT asset inventory for reconciliation to the ARM. When you use IT Asset Management with Maintenance Management, the repository stores organizational asset information including physical and financial definitions, acquisition history, and maintenance history. IT Asset Management provides a central workspace to manage and deploy IT Asset Management systems, view discovered and reconciled results, monitor collected metrics, and drill down to detailed asset data for problem solving and information gathering activities. This interactive workspace collects detailed hardware and software inventory information and authorized versus unauthorized license deployment with access to contract and warranty information relative to IT assets.

Oracle has partnered with network discovery tool suppliers to perpetually inventory IT assets including software and hardware devices that connect to your network. After the discovery tool collects usage data, it is reconciled to the Asset Repository Manager by means of configurable business rules that define reconciling data-points. The asset reconciliation engine compares discovered asset inventory to that stored in the ARM, where all organizational assets are stored with complete business data, acquisition history, maintenance history, and financial data. Because IT assets are perpetually inventoried by means of network discovery tools, IT assets are always accurately reflected in business data and financial reporting.

This diagram shows the basic integration between Asset Management and IT Asset Management.

Image: IT Asset Management and Asset Management integration

Basic integration between Asset Management and IT Asset Management:



Note: You must use Asset Management before you can use IT Asset Management.

Related Links

"Understanding IT Assets and the Asset Repository (*PeopleSoft FSCM 9.2: IT Asset Management*)"

Integrating Asset Management with Maintenance Management

This topic provides an overview of how to integrate Asset Management with Maintenance Management.

Understanding How to Integrate with Maintenance Management

Asset Management integrates with Maintenance Management by creating service request and work order links between asset warranty claims or other asset maintenance events, and assets. Asset Management maintains assets in the Asset Repository, where they are accessible among the Asset Lifecycle Management (ALM) products, including Maintenance Management. Each asset record stores maintenance activity details and can be adjusted, transferred, or retired by Maintenance Management processes.

Work orders are used to track the costs associated with maintaining or creating assets. In Maintenance Management, a work order consists of multiple work order tasks with each task specifying the asset that is being maintained as well as a related project and activity. Each task is used to identify the transaction costs of performing the asset maintenance. These transaction costs flow from Maintenance Management into various systems including Asset Management. A work order task can specify only one asset, one project, and one activity, but any given asset, project, and activity can be maintained by multiple work orders or work order tasks. When an asset is selected from the Asset Management asset repository for maintenance or repair through a work order, Maintenance Management notifies the user of any warranties associated with the asset being worked on in the work order. You can then file warranty claims for the work performed to recover the cost of the work performed.

With a preventive maintenance schedule in place, Maintenance Management can automatically generate work orders and maintenance forecasts to help you ensure that your asset base is optimally maintained. You can set up resource requirements for a work order task for labor, materials, purchased or on-hand parts, and tools resources prior to scheduling these resources. To simplify this process, you can set up work order task templates that define these requirements for different types of tasks and problems. Another method of determining parts that may be required to repair an asset is accessing an Equipment Parts List (EPL), which is part of the Assets Management asset repository and lists the asset and any parts or other information associated with the asset. If special requirements are specified, this information can be copied forward to be used as the basis for scheduling those resources. When setting up requirements, you can indicate whether to calculate estimated costs either at the business unit level or at the shop level for labor, materials, and tools resources. The total estimated costs for each resource are accumulated in the work order's cost page. When each work order task is performed, the total actual costs for each work order task resource is also displayed on the work order's cost page, along with any variances between the two, and stored at the asset level within the asset repository.


Asset Management can record and attach meter readings to assets and force a preventive maintenance event if a meter falls outside the tolerance range defined on the Meter Type page. When a meter reading falls outside of the tolerance range, Asset Management creates a preventive maintenance work order. The system performs this function only when you have defined a preventive maintenance schedule ID for the asset with a range meter type assigned to the schedule ID. The Asset Repository enables you to require a meter for any kind of work order to complete the work order.

While Maintenance Management offers tactical reporting and analytics for understanding costs and effectiveness by shop and asset, the ability to analyze operations and costs across the enterprise is key to driving wholesale changes into the organization. Searches can be done to identify parts used anywhere in your entire organization. This information can be invaluable when you are trying to address the impact of a manufacturer recall or to ensure that a decision to upgrade a component is carried out consistently throughout the enterprise. The integrated Asset Repository Manager enables you to rapidly identify, access, and analyze your entire asset base. Separate financial and operational asset hierarchies within the asset repository enable financial users to view the asset base from one perspective and enable operations and maintenance users to view it from a totally different perspective.

This diagram shows how the Maintenance Management and Asset Management products integrate:

Image: Maintenance Management and Asset Management integration

Maintenance Management and Asset Management integration:



Related Links

"Integrated Product Setup Considerations (*PeopleSoft 9.2: Maintenance Management*)"

Integrating Asset Management with Real Estate Management

This topic provides an overview of how to integrate PeopleSoft Asset Management with PeopleSoft Real Estate Management, lists prerequisites, and discusses how to:

- Exchange asset data with CAFM.
- Establish space allocation basis for CAFM.
- Exchange property information with CAFM.
- Exchange department information with CAFM.

Pages Used to Integrate Asset Management with Real Estate Management

Page Name	Definition Name	Navigation	Usage
Basis Generation For Allocation Process	AM_SPC_ALLOC	Asset Management, Send/Receive Information, Load Interface, Space Allocation	Generate the cost basis for the space allocation process.
CAFM Property Integration	RE_REQ_SYNC_RUN	Asset Management, Send/Receive Information, Computer Aided Facility Mgmt, Property Integration	<p>Exchange property information with the CAFM application using these processes:</p> <ul style="list-style-type: none"> • <i>RE_REQ_ELOC</i> Request employee location from CAFM. • <i>RE_REQ_PROP</i> Request property size and occupancy from CAFM. • <i>RE_REQ_FPLAN</i> Request new and deleted properties from CAFM.
CAFM Department Integration	RE_PUB_DEPT_RUN	Asset Management, Send/Receive Information, Computer Aided Facility Mgmt, Department Integration	<p>Exchange department information with the CAFM application using the RE_PUB_DEPT process: This application engine process is a Full Sync of Department Tree that transfers the department tree specified for the selected business unit to CAFM so that their system understands the general departmental breakdown. With that information, the CAFM system can properly assign custodians to property assets and employees to spaces. CAFM cannot modify department data, because the FSCM tables are considered the master data.</p>

Page Name	Definition Name	Navigation	Usage
CAFM Employee Integration	RE_PUB_EMPL_RUN	Asset Management, Send/Receive Information, Computer Aided Facility Mgmt, Employee Integration	Exchange employee information with the CAFM application using the RE_PUB_EMPL process: The application engine process is a full sync of employees that transfers the employee data from the HR employee tables residing in FSCM. This data is provided to the CAFM system so that employees can be assigned to spaces on the floor plan when users are performing space management. CAFM cannot modify employee data, because the FSCM HR tables are considered the master data.

Understanding How to Integrate with Real Estate Management

Asset Management integrates with Real Estate Management by managing the defined property assets associated with Real Estate Management in the Asset Repository and by providing the integration with third-party CAFM software suppliers to manage employee/department to property assets information.

Real Estate Management utilizes Asset Management centralized Asset Repository Manager as the source of all operational and financial property asset information. The repository provides property tax tracking against each site or building stored. Using existing functionality in Asset Management, including express capitalization from Project Costing, enables companies to perform project management and then capitalize or expense the costs related to their properties accordingly.

Asset Management provides third-party CAFM integration through the centralized asset repository. The financial asset from the repository is used along with employee and department information from PeopleSoft Human Capital Management (HCM) as the source to the CAFM solution for space management. The property floor and space information and the employee space assignments performed in the CAFM solution are then updated automatically and sent back to the repository to provide a single source of information about accurate measurements of spaces within properties and timely assignments of employees in spaces. This information can then be passed to General Ledger for facility cost allocations based on square feet or meters per department as well as for providing an up-to-date space utilization model.

When creating a lease in Real Estate Management, you use the Asset Management centralized asset repository for property information. You can select the property from a list or enter the property information manually. For you to select the property from the list, properties must already exist in the repository through either manual entry or through the third-party CAFM integration. The properties are known to be valid as they are generated and stored in the repository in a controlled manner: through the capitalization processes between Project Costing and Asset Management, through the asset entry as a new acquisition, or through the third-party CAFM integration. The integration between Asset Management and the third-party CAFM provider also enables Real Estate Management to use information about the property assets captured in the Asset Repository such as size of spaces, location of assets within these spaces, and employee assignments to spaces.

The following list provides a high-level overview of the actual integration steps between Asset Management and the third-party CAFM provider:

- CAFM provides a listening connector for PeopleSoft Integration Broker that resides on the PeopleSoft web server.
- The predefined messages and transactions are tailored to the functional analysis of the data transmissions.
- Incoming messages to the PeopleSoft server that are from CAFM are directed to the connector by the Gateway server, which then sends the messages to PeopleSoft Target Connectors.
- In turn, the PeopleSoft Target Connectors deliver the messages to either Component Interfaces or are embedded directly into the corresponding tables.

The following information is exchanged between the two systems:

- Organizational information including the employee names and identification numbers, department assignments, and organizational hierarchy using the PeopleSoft department trees.
- Asset information for properties residing in the Asset Management centralized asset repository.

The CAFM solution then builds sites and buildings to the lower levels of floors and spaces, and updates any measurement and occupancy information.

- Employee or department assignments to properties.


Once assigned and returned from CAFM to Asset Management, this data is used to update the custodians of the various property assets. A department can be assigned to the custodian for a building, floor, space, and so on, but if an employee is assigned to a particular space, his or her department can override the default department set as the custodian. This information can then be used by General Ledger as the basis for cost allocations using tables residing within the asset repository.

For more complex facility allocations factoring in common or shared space, the third-party CAFM provider reports can be imported into the general ledger as the space allocation basis.

The following diagram displays the process flow for Real Estate Management integration:

Image: Asset Management and Real Estate Management integration points

Process flow for Real Estate Management integration:



Related Links

"Understanding Product Integration (*PeopleSoft FSCM 9.2: Real Estate Management*)"

Exchanging Asset Data with CAFM

Asset Management shares the asset repository with Real Estate Management. The asset repository integrates with a third-party computer aided facilities management (CAFM), sending space allocation information for defined property assets as well as employee and department information. In turn, the CAFM application passes updated space allocation information for existing assets as well as new "sub" assets, such as floor, space, and area, with the measurements from the CAFM application, and the employee assignments to the "sub" assets, back to the PeopleSoft application.

The asset repository supports integration with Real Estate Management by enabling asset property records (ASSET_PROPERTY) to have asset components. A one-to-one relationship exists between an asset and the asset property. During asset creation, when the asset type *Property* is selected, the Property Information tab is enabled. Information relating to the property asset as well as property tax information is stored here.

Note: Defining an asset as property is available only from the Asset Basic Add component.

The integration has the following impacts on the asset repository:

- Nonstructural assets are assigned to properties as a component of the property asset, and the property asset includes a defined location.

The assignment of nonstructural assets to structural assets is done through the Component Of ID field in the asset table. A nonstructural asset will have its component of ID set to the asset ID of a structural asset. In this way, the nonstructural asset is located at that property. The component of ID has only one key, the ASSET_ID. The system assumes that nonstructural assets belong to the same business unit that owns the property. When you are integrating with CAFM solutions, only structural assets are supported.

- The asset repository requires that the property asset definition also include an associated employee or asset custodian.

The asset custodian (ASSET_CUSTODIAN) is a child table of the asset table and allows an N-1 relationship between employees (custodians) and the assets. When you are exchanging information with CAFM, new employee information linked to a property updates the asset custodian table.

To support these functions, the following rules apply:

- You can view the allocation basis from the (RE_ALLC_BASIS_VW) page in Real Estate Management.

Use the allocation feature in General Ledger to set up your own allocation process using this view as the basis. The allocation basis record is populated in the following way:

- The statistics code and statistical account comes from the fields defined for the asset property business unit.

The statistics amount comes from the sum of the total area of all properties using the same statistical account.

- If an employee is the custodian of the property, the employee ID, business unit, and department ID are derived from the employee tables defined in HCM. If a property does not have an employee associated as a custodian, then the department ID of the asset custodian is used.

See "Define Allocation Step - Basis Page (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

- When an employee moves out of a space, the employee ID that is defined in the asset custodian table is cleared, and the department ID of the first parent property that has a department ID assigned to it is used for the current property.

If none of the parent properties have a department ID, it is left blank.

- When you are viewing the general ledger allocations, the view itself is the current value of the department space usages.

You can use the Space Allocation report to search over this view.

See "Producing Allocations Reports (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

Prerequisites

Before you can use the space allocation link with CAFM utilities, you must:

1. Complete the installation of CAFM to set up the appropriate integration messages between PeopleSoft software and the CAFM application.

See *PeopleSoft Financials, ESA, and Supply Chain Management Product-Specific Installation Instructions, "Integrating PeopleSoft Asset Management With Space Management Solution."*

2. Enable Space Management integration with Asset Management on the Installation Product Options page for Asset Management (INSTALLATION_AM) in the installation component (INSTALLATION).

See "Installation Options - Asset Management Page (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

3. Establish the statistics code and statistical account for Space Allocation for each Asset Management business unit on the Interface Options page (BUS_UNIT_INTFC_OPT) of the define business units component (BU_DEFN).

See Understanding Asset Management Business and Cash Generating Units.

4. Enable and define or modify trees with business units from which properties and employees will be used to exchange information with CAFM.

See Understanding Asset Management Business and Cash Generating Units.

See "Department Page (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

See *PeopleTools: PeopleSoft Tree Manager*

5. Establish asset types and subtypes within Asset Management to define property assets.

See Understanding Asset Processing.

6. Establish active property assets with designated types and subtypes in the asset repository.

See "Understanding Adding and Maintaining Assets (*PeopleSoft FSCM 9.2: Asset Management*)".

7. (Optional) Record property taxes associated with property assets using the Record Property Taxes page and component (ASSET_PROP_TAX).

See "Understanding Adding and Maintaining Assets (*PeopleSoft FSCM 9.2: Asset Management*)".

Establishing Space Allocation Basis for CAFM

Use the Basis Generation For Allocation Process page (AM_SPC_ALLOC) to generate the cost basis for the space allocation process.

Navigation

Asset Management, Send/Receive Information, Load Interface, Space Allocation

Use a run control definition to establish the space allocation cost basis. The space allocations exchanged with the CAFM application can be measured by square feet, meters, or any other measurement that suits your organization. This process determines how the actual space allocated by the CAFM application should be measured.

CAFM creates the space allocations and passes them back to the PeopleSoft application. The allocation is then used to calculate the cost, for example, per square foot used by a specific department or resource. The information can then be used by General Ledger in the allocation process and in generating financial statistics and reports.

CAFM Property Integration Page

Use the CAFM Property Integration page (RE_REQ_SYNC_RUN) to .

Navigation

Asset Management, Send/Receive Information, Computer Aided Facility Mgmt, Property Integration

Image: CAFM Property Integration page

This example illustrates the fields and controls on the CAFM Property Integration page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'CAFM Property Integration' page. At the top, there are links for 'Run Control ID', 'CAFM', 'Report Manager', and 'Process Monitor', along with a 'Run' button. Below this is a table with the following structure:

CAFM Property Integration	
Description	Sync Option
Request for Employee Location from CAFM	Incremental Sync
Request for Property Size and Occupancy from CAFM	Incremental Sync
Request for New and Deleted Properties from CAFM	Incremental Sync

Below the table, there are links for 'Message Monitor' and 'Return to Computer Aided Facility Mgmt'.

Each process name to be run and its description is displayed.

Sync Option

Select the integration broker message type to use. The options are:

- *FullSync*

A full synchronization message exchanges all information even if it has not changed since the last time the information was requested. The exception for this rule is that when you are requesting new properties, full sync will act like an incremental sync.

- *Incremental Sync*

An incremental synchronization message exchanges only information that has changed since the last time the information was requested.

When you run the process, the requested CAFM data updates the following PeopleSoft tables:

- *ASSET*
- *ASSET_CUSTODIAN*
- *ASSET_LOCATION*
- *ASSET_PROPERTY*
- *ASSET_ACQ_DET*

CAFM Department Integration Page

Use the CAFM Department Integration page (RE_PUB_DEPT_RUN) to exchange department information with the CAFM application using the RE_PUB_DEPT process: This application engine process is a Full Sync of Department Tree that transfers the department tree specified for the selected business unit to CAFM so that their system understands the general departmental breakdown.

With that information, the CAFM system can properly assign custodians to property assets and employees to spaces. CAFM cannot modify department data, because the FSCM tables are considered the master data.

Navigation

Asset Management, Send/Receive Information, Computer Aided Facility Mgmt, Department Integration

Image: CAFM Department Integration page

This example illustrates the fields and controls on the CAFM Department Integration page. You can find definitions for the fields and controls later on this page.

Business Unit GL

Select the associated GL business unit from which employees are selected to exchange information.

Tree Name

Select the appropriate Department tree from which employees selected are to exchange information.

Note: If you select a tree other than Department, the process will fail.

Exchanging Employee Information with CAFM

Use the CAFM Employee Integration page (RE_PUB_EMPL_RUN) to exchange employee information with the CAFM application using the RE_PUB_EMPL process: The application engine process is a full sync of employees that transfers the employee data from the HR employee tables residing in FSCM.

This data is provided to the CAFM system so that employees can be assigned to spaces on the floor plan when users are performing space management. CAFM cannot modify employee data, because the FSCM HR tables are considered the master data.

Navigation

Asset Management, Send/Receive Information, Computer Aided Facility Mgmt, Employee Integration

The employee integration with CAFM does not require the input of any parameters.

Processing PeopleSoft Asset Management, Purchasing, and Payables Transactions

This topic provides an overview of PeopleSoft Asset Management, Payables, and Purchasing transactions and discusses how to:

- Process PeopleSoft Payables transactions with PeopleSoft Asset Management.
- Process PeopleSoft Asset Management Lease Payments in PeopleSoft Payables.
- Process PeopleSoft Purchasing transactions with PeopleSoft Asset Management.

Understanding PeopleSoft Asset Management, Purchasing, and Payables Transactions

PeopleSoft Purchasing sends receipts to PeopleSoft Asset Management as either capitalized or noncapitalized assets. If noncapitalized assets are created from Purchasing, these assets can be capitalized when the voucher information is received from Payables.

Note: PeopleSoft Asset Management automatically capitalizes assets created from PeopleSoft Payables as long as the asset profile used can be capitalized. Additionally, retirement transactions communicated from AP/PO to AM represent only closed vouchers if that action was selected at the business unit level and canceled receipts.

See [Interface Options Page](#).

See "PeopleSoft Purchasing Integrations (*PeopleSoft FSCM 9.2: Purchasing*)".

The PeopleSoft Asset Management integration with PeopleSoft Purchasing and Payables:

- Provides the ability for requesters and buyers to group requisition and purchase order lines that correspond to a single asset. See "Setting Up Procurement Groups (*PeopleSoft FSCM 9.2: Purchasing*)".

- Allows Purchasing to determine when assets should be created based on the receipt of a procurement group sequence.
- Allows flexible allocation of asset-applicable voucher adjustments, if enabled in Payables. See "Allocate Asset Page (*PeopleSoft FSCM 9.2: Payables*)".
- Provides email notification of asset-applicable credit memos to improve visibility to credit transactions that may require further review or action.
- Permits the full text of procurement item descriptions to populate the asset detailed description field. (Location/Comments/Attributes page.)
- Streamlines business processes to track requisitions and purchase orders associated with assets, asset voucher adjustments and the notification of returns to trigger asset retirement transactions.

This topic discusses the following process flows:


- Consolidating Requisition and Purchase Order Lines for Asset Components.
- PeopleSoft Payables Transactions in PeopleSoft Asset Management.
- PeopleSoft Asset Management Lease Payments in PeopleSoft Payables.
- PeopleSoft Purchasing Transactions with PeopleSoft Asset Management.

Before you can integrate Asset Management with Purchasing and Payables transactions, you should be familiar with the flow of data from PeopleSoft Purchasing to PeopleSoft Asset Management as well as the flow of data from PeopleSoft Payables to PeopleSoft Asset Management. The data flow conforms to the logical steps that you take to create integrated transactions between Asset Management and these applications.

The following diagram shows the process flow between Asset Management, Purchasing and Payables:

Image: Data Flow Between Asset Management, Purchasing, and Payables

Data Flow Between Asset Management, Purchasing, and Payables



Consolidating Requisition and Purchase Order Lines for Asset Components

An individual asset’s cost can be associated with multiple requisition and purchase order lines on one or multiple requisitions and purchase orders. PeopleSoft provides the ability for requesters and buyers to group requisition and purchase order lines that correspond to a single asset by using a Procurement Group. Purchasing can also determine when assets should be created based on the receipt of a procurement group sequence. See Purchasing documentation, "Setting Up Procurement Groups (PeopleSoft FSCM 9.2: Purchasing)".

To facilitate the identification of procurement items that correspond to individual assets, Purchasing, Payables, and eProcurement include fields, pages and components to manage Procurement Groups. As items are received, the new receipt lines display the Procurement Group details that are associated with the corresponding purchase order line. The receiving process allocates the received goods and services by asset for integration with Asset Management.

When copying purchase order or receipt information to a voucher in PeopleSoft Payables, the Procurement ID information can be copied to the voucher line. See "Copying Asset-Applicable Vouchers from Purchase Orders and Receivers (*PeopleSoft FSCM 9.2: Payables*)".

Receiver Interface Push Process

The Receiver Interface Push (PO_RECVPUSH) process accommodates Procurement Groups. When an item is flagged as a primary item, a separate transaction is inserted into the INTFC_PRE_AM record in increments of the unit allocation quantity or amount if the Allocate Purchasing Group option is enabled on the Purchasing Options page. See "Purchasing Options Page (*PeopleSoft FSCM 9.2: Purchasing*)".

The allocation quantity (or amount) units have already been parsed in the Receipt Asset Lines (by online Receipts) by this point (also contingent on the Allocate Purchasing Group option). The Receiver Interface Push process then moves that data to the INTFC_PRE_AM record, reconciles remainders (fractional allocation quantities or amounts), and assigns each transaction a Procurement Group Sequence. Each non-primary item in the procurement group is assigned the Procurement Group Sequence that is associated with the primary unit.

See "Using the Receiver Interface Push Application Engine Process (PO_RECVPUSH) (*PeopleSoft FSCM 9.2: Purchasing*)".

Note: The procurement group sequence is calculated as the next available sequence associated with that procurement group. The process updates the procurement group sequence number on the INTFC_PRE_AM record as well as the Receipt Asset Line record (RECV_LN_ASSET) so that the two tables are kept in sync.

Once all of the items in the Procurement Group for an asset have been inserted into INTFC_PRE_AM, the status of the items for each allocation unit is updated to *PO Group Incomplete* if any of the following conditions exist:

- The primary item has not yet been pushed for that allocation unit.
- A fractional allocation unit quantity (or amount) exists for one of the items for that allocation unit.
- Not all of the items that make up the procurement group have been pushed (for a particular allocation unit). The Receiver Interface Push process examines all of the PO lines in the system (and requisition lines with open quantity or open amount for Amount Only lines) to determine the composition of the procurement group.

See [Pre-AM Financial Page](#) and [Pre-AM Physical Page](#).

PeopleSoft also provides Procurement Group Inquiry components to review Procurement Group details and status in Asset Management, Purchasing, and Payables.

See [Procurement Group Inquiry Page](#)

Example of Consolidated Multiple Purchase Order Lines for Asset Components

Consider the following example. You set up a procurement group and items associated with a Procurement Group Sequence are received on November 15, 2012. The Transaction, Accounting, In Service, Acquisition and Placement Dates for the asset are set to November 15, 2012.

The status of the associated pre-interface rows is updated automatically from *On Hold* (HLD) to *Pending* (NEW) by the Receiver Interface Push process.

Pre-Interface		System Source	Load Status	Transaction Date	Accounting Date	Procurement Group	Procurement Group Sequence	Primary Unit
ID	Line							
1	1	PPO	New	10/3/2012	10/3/2012	AC-ASSET1	0001	Y
2	1	PAP	New	9/29/2012	10/3/2012	AC-ASSET1	0001	Y
3	1	PPO	New	10/12/2012	10/12/2012	AC-ASSET1	0001	N
4	1	PAP	New	10/01/2012	10/13/2012	AC-ASSET1	0001	N
5	1	PPO	New	11/15/2012	11/15/2012	AC-ASSET1	0001	N

The PO/AP/AM Interface (AMPS1000) is then run to populate the INTFC_FIN and INTFC_PHY_A tables.

Interface ID	Business Unit	Asset ID	Load Type	System Source	Load Status	Transaction Date	Accounting Date	Procurement Group	Int Service Date
10000006	US001	NEXT	FAD	PAP	New	9/29/2012	10/3/2012	AC-ASSET1	9/29/2012
10000006	US001	NEXT	FAD	PAP	New	10/01/2012	10/13/2012	AC-ASSET1	10/1/2012

Interface ID	Business Unit	Asset ID	Load Type	System Source	Load Status	Procurement Group	Procurement Group Sequence	Primary Unit	Acquisition Date
10000006	US001	NEXT	FAD	PAP	New	AC-ASSET1	0001	Y	9/29/2012

Interface ID	Business Unit	Asset ID	Load Type	System Source	Load Status	Procurement Group	Procurement Group Sequence	Primary Unit	Acquisition Date
10000006	US001	NEXT	FAD	PAP	New	AC-ASSET1	0001	N	10/1/2012
10000006	US001	NEXT	NAD*	PPO	New	AC-ASSET1	0001	N	11/15/2012

* Procurement item was received to complete the Procurement Group AC-ASSET1 sequence 0001, but the invoice was not yet received.

Transaction Loader sets the Transaction, Accounting, In Service, Acquisition and Placement Dates assigned to the asset created for Procurement Group AC-ASSET1 sequence 0001 in this example to 11/15/2012. The asset profile assigned to a Procurement Group's Primary Unit becomes the default asset profile for the new asset that is created.

Each Procurement Group Sequence represents a unique row on the COST and ASSET_ACQ_DET tables.

Business Unit	Asset ID	Book	Trans Type	Trans Date	Accounting Date	Quantity	Cost
US001	000000000113	CORP	ADD	11/15/2012	11/15/2012	2	150.00
US001	000000000113	CORP	ADD	11/15/2012	11/15/2012	2	400.98
US001	000000000113	CORP	ADD	11/15/2012	11/15/2012	1	988.34

Business Unit	Asset ID	Seq	PO BU	Purchase Order	PO Line	Quantity	Amount
US001	000000000113	0	US001	000000233	1	2	150.00
US001	000000000113	1	US001	000000233	3	2	400.98
US001	000000000113	2	US001	000000234	1	1	988.34
US001	000000000113	3*	US001	000000235	1	1	29.99

*Procurement item received to complete the Procurement Group AC-ASSET1 sequence 0001, but invoice not yet received.

Once the asset is created for the Procurement Group Sequence, any subsequent invoices processed by Payables will continue to be interfaced to Asset Management. Each invoice will represent a new cost row on COST.

Note: You can use the Purchasing, Payables, and Asset Management inquiries to review Procurement Groups and their statuses. Asset components that are not included in a Procurement Group should be associated with the corresponding asset(s) manually.

Related Links

[Consolidating and Unitizing Assets](#)

Processing PeopleSoft Payables Transactions with Asset Management

Asset Management enables you to add assets en masse directly from existing accounts payable vouchers. To do so, accounts payable voucher information is loaded into Asset Management by using the Payables/Purchasing Interface.

Note: If you are using Project Costing to capture data on your asset-related POs and receipts, the system passes purchasing and receipts data through the Projects to Asset Management interface rather than the Payables/Purchasing Interface. In this way, the PeopleSoft system provides the navigation from the Asset Acquisition Detail page to POs and receipts, as well as the associated projects.

To send asset information from Payables to Asset Management:

1. Identify the voucher lines as asset-related in Payables.

This enables you to enter asset information on the Voucher Invoice Information page.

You do not need to enter the asset ID on the receiver or voucher pages unless you want to:

- Specify your own, unused asset ID on the receiver or voucher instead of using the *NEXT* asset ID available in PeopleSoft Asset Management.

If split-funding is enabled for the batch process, the asset ID is appended with a sequence number to identify multiple distribution lines to a single asset for cost and depreciation allocation.

- Add additional cost to an existing asset.

For example, suppose that the receiving clerk enters an unused asset ID on a receipt unbeknownst to the payables clerk entering the voucher. The payables clerk leaves the asset ID as *NEXT* on the voucher, and the asset ID entered in Receiving is carried through to PeopleSoft Asset Management.

In most cases, the most reliable practice is to leave the asset ID as *NEXT* on the receiver *and* voucher pages, and PeopleSoft Asset Management assigns the next asset ID when the Transaction Loader is run.

For example, suppose that you create a purchase order (PO) and receive 10 computers. The computer is a serialized item and the PO Business Unit option is set to *not* capitalize at the point of receipt. When you select Create Assets in Receiving, you see 10 lines on the receiver page; 10 interface lines are then sent to Asset Management. If these lines are fully processed into Asset Management, 10 nonfinancial assets would be created from Receiving, and the Transaction Loader would have assigned the next 10 unused asset IDs for the AM business unit. Generally, when you create a voucher for 10 computers, you commonly enter one line with a quantity equal to 10, unless the computers are going to different departments. Because the receiver or PO is copied onto the voucher, the PO and receiver entries are sent to Asset Management when the voucher data is sent. Sending these receiver and PO entries enables the single line from Payables to match and capitalize the 10 assets created earlier, because the PO and receiving keys are stored in acquisition detail. Oracle recommends that you copy the receiver onto the voucher for more information available to match the PO and AP data; doing so allows for a more detailed navigation from the Asset Acquisition Detail page. Oracle also recommends copying the receiver

onto the voucher when multiple receivers exist for a PO, and doing this is essential when you are matching multiple vouchers to a PO.

If, as in the preceding example, the receiving and voucher data is processed and transferred to AM at the same time, the 10 lines from Purchasing Receiving and the single line from Payables are grouped together for matching in AM processing to create 10 financial assets from Payables. Follow these steps:

2. Save and approve the voucher.
3. Run matching (depending on your setup options), and post the voucher to accounts payable.

Warning! If the voucher data being sent to Asset Management relates to previous assets that were created from Purchasing, the voucher *must* be matched to the PO and receiver. There can be no overrides with respect to receivers or receiver quantities exceptions. If encountered, Accounts Payable Receiver Match Exceptions RULE_R500 or RULE_R600 must not be overridden on asset-related vouchers; this interface cannot properly match up PO, receiver, voucher, and asset data with receiver match exceptions that have been overridden. Duplicate assets may result.

Note: If matching is not required for the supplier, you cannot use the Copy Receiver function when copying to a voucher. You can use only the Copy PO function to copy PO distribution lines. Oracle recommends that when creating vouchers for asset-related items, you copy the voucher information from the receiver, with the understanding that in some cases only the PO is available in Payables. If only the PO is copied onto the voucher, Payables must associate receivers with the vouchers.

4. Run the Load Assets Application Engine process (INTFAPAM) to populate the Asset Management Pre-Interface Loader table (INTFC_PRE_AM).

The Pre-Interface Loader determines the appropriate type of asset transactions to be loaded into the Asset Management Loader Tables, based on the voucher information and comparing it to the receiving information.

You can process adjustments by first unposting the vouchers, making changes to them, and then reposting and sending the adjustments to Asset Management. Rematching, if applicable, is also required.

When a voucher that was already sent to Asset Management is closed, the asset that was originally created by the voucher results as a negative addition, retirement, or no transaction. The appropriate action is defined during system setup on the Establish Business Units, Interface Options page.

If the initial posting and unposting are processed in the same run of AMPS1000, no asset is created because the two transactions cancel each other out. Load status for the first posting entry is set to *Consolidated*; load status for the unposting and closing entry is set to *Done*.

When a voucher that has previously been distributed to Asset Management is unposted and the ChartFields are changed, corresponding asset transfers are not handled. Asset transfers can be made only in the Asset Management system. In addition, once an asset has been capitalized from the PO, you cannot change the profile on the receiver or voucher pages, nor can you create a subsequent voucher to affect this asset with a new profile. Ensure that profiles are correct on the PO and in the item master catalog.

5. Preview the data in the Pre-Interface table, and make corrections as needed.

See [Pre-AM Financial Page](#) and [Pre-AM Physical Page](#)

6. Run the Payables/Purchasing Interface process (AMPS1000_RQST) from Asset Management, Send/Receive Information, Retrieve Info from AP/PO.

This process loads the Transaction Loader tables (INTFC_FIN and INTFC_PHY_A). Every voucher line becomes a *Pending Asset Load* transaction, with book and cost information entered automatically according to the asset profile ID, cost, and quantity on the voucher. If your profile ID uses multiple books, then multiple book and cost information is generated. If an existing asset ID is specified on a voucher, then the cost associated with that voucher is added to the existing asset as a cost adjustment transaction.

Asset Management assigns asset cost as:

$$(\text{Asset Cost}) = (\text{Sum of Item Costs}) + (\text{Use Tax}) + (\text{Sales Tax}) + (\text{Freight}) + (\text{Miscellaneous Charges}) + (\text{Nonrecoverable VAT})$$

7. Preview data in the loader tables, and approve load lines.
8. Run the Transaction Loader (AMIF1000) to load these transactions into the Asset Management tables.

Note: Because the Payables Interface sets the default profile switch to *Yes* in the load tables, all books on the Transaction Loader asset profile automatically appear by default for each asset. In addition, all lines appear as automatically approved.

Warning! Ensure that if any of the assets that you are adding through the Payables/Purchasing interface include references to foreign currency, the exchange rate for that currency is defined in the currency exchange rate tables. If an exchange rate has not been defined, the assets will not populate the PS_COST table.

See "Journal Source - Currency Options Page (*PeopleSoft FSCM 9.2: Application Fundamentals*)".

Note: 1. You can enable PeopleSoft Payables to provide automatic email notification of asset-applicable credit memos to the Property Office when an asset is returned. created in PeopleSoft Payables are not sent to PeopleSoft Asset Management by way of the Payables Application Engine. The asset manager should make these adjustments manually in the Cost Adjust/Transfer component This improves visibility to credit transactions that may require further review or action. See "Load Assets Request Page (*PeopleSoft FSCM 9.2: Payables*)". See also [Interface Options Page](#)

2. AMPS1000 interprets asset sequence numbers when assigning NEXT asset ID. Asset IDs for split-funded assets using the asset ID sequence number to associate multiple distribution lines to a single asset ID are assigned in this step of the interface process.

3. Each distribution line entered in Payables for a split-funded asset will become a different cost line in Asset Management. If the same ChartFields are used for the different lines, the integration process will not consolidate the Cost lines.

Related Links

"Journal Source - Currency Options Page (*PeopleSoft FSCM 9.2: Application Fundamentals*)"

"Understanding Voucher Build Processing (*PeopleSoft FSCM 9.2: Payables*)"

"Understanding Adding and Maintaining Assets (*PeopleSoft FSCM 9.2: Asset Management*)"

Processing PeopleSoft Asset Management Lease Payments in PeopleSoft Payables

The integration between PeopleSoft Asset Management lease payments and PeopleSoft Payables automatically generates vouchers for lease payments that are calculated in Asset Management, including both capital and operating leases. In addition, the lease payment schedule segregates the principal and interest of each payment, which are used by the AMDPCLOS process to generate the payment accounting entries. The payments can be allocated on a monthly basis, depending upon your setup of payment schedules.

To configure Asset Management for the integration of lease payments with PeopleSoft Payables:

1. Set up the lease payment options for the Payables integration on the Interface Options page of the AM Business Unit Definition component (Set Up Financials/Supply Chain, Business Unit Related, Asset Management, Asset Management Definition, Interface Options).

The integration sends to Payables the information that is stored in the book that is defined as the Lease Book on the AM Business Unit Definition page.

- a. Select the Lease Interface Processing check box to enable the integration for the business unit.
- b. Select whether to auto approve vouchers.
- c. Enter the default Payables business unit.

See [Interface Options Page](#).

2. Set up the Payables Integration page within the Leased Assets components when adding or updating a leased asset (Asset Management, Asset Transactions, Leased Assets).

The Payables Integration page is visible only after Lease Interface Processing is enabled for the business unit.

See "Integrating Lease Payments with PeopleSoft Payables (*PeopleSoft FSCM 9.2: Asset Management*)".

See "Lease Payment Integration with PeopleSoft Payables (*PeopleSoft FSCM 9.2: Asset Management*)".

3. Add the Lease Interest Contra and Lease Obligation Contra accounts as clearing accounts.

Both accounts are credited in AM and debited subsequently during the voucher posting process in Payables.

See [Accounting Entry Templates Page](#).

4. Select whether to prorate the lease expense on the lease payment schedule (Set Up Financials/Supply Chain, Product Related, Asset Management, Payment Schedules).

This determines whether the accounting entries that are generated for lease payments by the depreciation close process prorate the interest or payment expense on a monthly basis (in accordance with GAAP).

See [Payment Schedules page](#).

To process the lease payments through the Asset Management integration with Payables:

- Approve the lease payments before sending them to Payables using the Approve Payments page (if the auto approve vouchers option is not selected for the business unit).
- Once the lease payments are ready to be processed, upload them to the Payables staging tables using the Lease Payments to Payables run control page.

This process populates the voucher build integration tables. It also updates the status of the integration depending on the processing results. The status is displayed on the Lease Payment Schedule page [ASSET_LEASE_03] and editable from the Review Payments page.

- Review the status of the lease payments on the Review Payments page. You can update the status from this page if the payments have not yet been approved or processed.

See "AP/AM Payment Reconciliation Page (*PeopleSoft FSCM 9.2: Asset Management*)".

- Asset Management provides Payables with the AM business unit, asset ID, payment date, accounting date, interest and principal obligation amounts, transaction currency, market rate type, market rate index, Payables business unit, supplier ID, and voucher ID. Therefore, all the aforementioned fields are required before you save at the asset level when the integration to Payables option is selected.
- The integration extracts the payment data from the Lease Payment Schedule table. Payables continues the process from the voucher build staging tables to obtain the corresponding vouchers. When the vouchers are generated, Payables adds the voucher ID to the Asset Management records.
- PeopleSoft Payables assigns an origin source for vouchers coming from the lease payment integration with AM to avoid the potential risk of resending these lease payments to AM as adjustments to existing assets.
- The Lease ID displays on the Payables Invoice Information page (VCHR_EXPRESS1). This field appears only when the voucher origin source for lease payments from Asset Management is invoked in update mode.
- Run the reconciliation process that compares the lease payment information that is sent from Asset Management to Payables with the voucher information that is stored in the Payables tables. This process creates the AM/AP Payment Reconciliation report (Asset Management, Financial Reports, Leased Assets, AP/AM Payment Reconciliation).

Processing PeopleSoft Purchasing Transactions with PeopleSoft Asset Management

Asset Management enables you to add assets from existing POs and receipts.

Note: If you are using PeopleSoft Projects to capture data on asset-related POs and receipts, the system passes purchasing and receipts data through the Projects-to-Asset Management interface rather than directly from the Payables or Purchasing interface. In this way, the PeopleSoft system provides the navigation from the Asset Acquisition Detail page to POs and receipts, as well as the associated projects.

To send purchasing information to Asset Management:

1. Generate a PO for the asset in Purchasing.

The PO should include the relevant AM business unit, profile ID, CAP number, sequence number, tag number, employee ID, capitalization status, and cost type.

If the quantity on the requisition is one, enter an asset tag number on the requisition to enable the PO and the receiver to appear by default.

Note: You can specify a CAP number and sequence number on a requisition (or a PO, if you do not use a requisition) in Purchasing to tie an asset to a budget. The system then passes the CAP information from the requisition to the PO to the receiver, and then into Asset Management.

2. Send the PO to the supplier.
3. When you receive the asset, enter it as *Received* in Purchasing.

The asset information specified on the PO appears by default to the receiver; you can record additional asset information on the receiving pages of Purchasing.

4. Run the Receiver Interface Push Application Engine process (PO_RECVPUSH) in Purchasing.

This process loads receiver lines into the Pre-Interface table (INTFC_PRE_AM).

Note: The Receiver Interface Push process can be run in multiple ways. If you are processing a receipt that has no inventory-related lines, the Receiver Interface Push process is used. If you are processing a receipt that has both inventory-related lines and asset-related lines, the Receiver Interface Push process runs as part of the Receipts Assets and Putaway process.

5. Run the Pre-Interface table (INTFC_PRE_AM) process.

Preview the data in the Pre-Interface table, and make corrections as needed.

Note: The Receiver Interface Push application engine process (PO_RECVPUSH) must be run to send receiver information related to a purchase order to PeopleSoft Asset Management. Both the Receiver Interface Push process and the Payables to Assets Interface process must be run when the voucher is created from a PO.

6. Run the Payables/Purchasing Interface process (AMPS1000).

This process loads the Transaction Loader tables (INTFC_FIN and INTFC_PHY_A).

7. Preview data in the loader tables, and adjust the approval status if necessary.

Interface IDs appear with a status of *Pre-approved*. Set them to *Unapproved* on the Financial and Physical A Approval pages as needed.

8. Run the Transaction Loader process (AMIF1000) to load these transactions into the Asset Management tables.

Note: Because the Purchasing Interface sets the default profile switch to *Yes* in the load tables, the Transaction Loader automatically retrieves by default all book information defined on the asset profile for each asset created. In addition, all lines received are automatically approved.

Although capitalizing at the point of receipt is not a recommended accounting practice, an asset entered through Purchasing may be either capitalized or uncapitalized. Two ways are available to do this. The

Capitalize check box on the PeopleSoft Purchasing Business Unit page enables you to specify that items are capitalized at the point of receipt. If an item is to be capitalized at the point of receipt, a financial asset is created when the receiver lines are loaded by the Transaction Loader. If an item is not capitalized at time of receipt, you can capitalize it later by either of the following methods:

- If your system is integrated with Payables, run the Payables Interface once a voucher has been entered for this asset, followed by the Pre-Interface and Transaction Loader to load the data.

The asset is capitalized automatically by means of the cost information entered on the voucher.

- You can capitalize the asset manually by using the Asset Basic Information component.

This method is not recommended if you have Payables and use the interface from Payables to Asset Management.

Assets are capitalized and depreciated based on actual cost and the date on which the asset is placed in service. This assumes that the asset has been received and invoiced by the supplier. Capitalization of an asset can include asset cost plus freight, taxes, and adjustments for installations. Each of these items may be treated differently for financial and tax purposes and can be determined only from the supplier's invoice.

Capitalizing an asset from PO cost may overstate or understate the asset account on the balance sheet because the final invoice cost has not been received. When the asset has been received and invoiced, it can then be capitalized correctly and depreciated by means of the actual invoiced costs. Additionally, if the asset has been capitalized upon receipt with differing ChartField information at the time of invoicing, it requires that the financial designation of the asset be finalized on the requisition.

If an asset has been received but not invoiced, it is included in the receipt accruals posted to the general ledger, but they are not yet capitalized. GAAP and FASB do not specifically support this accounting treatment; however, a standard recommendation is to maintain proper independent documentation that supports all recording of assets and expenses.

If an asset is created from PeopleSoft Purchasing, and it is serialized (or unitized later in Asset Management), and the corresponding voucher line's cost is different from the receiving amount, the difference is distributed to all assets created from the receipt.

The serialization attribute on the item is the easiest, most efficient, and most effective way to use the interface. The serialization attribute also streamlines the business process. Unitization or consolidation should be necessary only if you have not installed Purchasing, because PeopleSoft Purchasing serializes or leaves items and assets consolidated for the entire process.

Items used in this interface should be properly established in the item master catalog.

When an item is created, it can be classified as an asset by assigning an asset profile ID on the Purchasing Attributes page. An item can also be specified as serial-controlled on the Item Definition - Inventory: Tracking/Description page. Verify that the item ID is classified correctly prior to receiving assets. This saves you much time and eliminates such processes as Unitization and Consolidation. If, for example, you receive five items and the PO/AM interface should create five individual assets as opposed to one asset with a quantity of five, then the item ID should be serial-controlled, and it should also have an asset profile ID assigned in Purchasing Attributes.

However you choose to capitalize, understand that once an asset has been capitalized in Asset Management, you cannot subsequently change related asset or ChartField information in the subsystems.

In other words, asset transfers are not performed from PeopleSoft Purchasing or Payables; transfers are handled only in PeopleSoft Asset Management.

If an asset is split-funded, the batch process generates the next asset ID based upon a subordinate sequence number identifying multiple distribution lines to a single asset allowing asset cost to be split across all identified accounting distributions.

Note: Nonfinancial assets that are created in Purchasing (not capitalized at the point of receipt) automatically display a status of *Received*. The asset remains in *Received* status until the asset is paid or the decision is made to capitalize the asset. When the asset is invoiced in Payables and that invoice information is processed by the PO/AP/AM interface, the status of the asset is updated to *In Service*, and the asset is capitalized (if the asset profile is that of a capitalized asset). Asset Management does not make adjustments for existing assets from the PO interface. The process only adds new assets.

Related Links

"Asset Management Information for Line Page (*PeopleSoft FSCM 9.2: Purchasing*)"

Processing Purchasing and Payables Transactions with Asset Management

This topic discusses how to:

- Preview data in the Pre-Interface table.
- Run the Payables/Purchasing interface (AMPS1000).

Pages Used to Process Purchasing and Payables Transactions with Asset Management

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Pre-AM Physical	INTFC_PRE_AM_01	Asset Management, Send/Receive Information, Preview AP/PO Information, Pre-AM Physical	Preview the physical asset data in the Pre-Interface PreAM 1 table.
Pre-AM Financial	INTFC_PRE_AM_02	Asset Management, Send/Receive Information, Preview AP/PO Information, Pre-AM Financial	Preview the financial asset data in the Pre-Interface PreAM 2 table.
Payables/Purchasing Interface	RUN_AMPS1000	Asset Management, Send/Receive Information, Retrieve Info from AP/PO	Run the Pre-Interface Loader to load the data (from Payables or Purchasing) into the Asset Management Loader tables.

Page Name	Definition Name	Navigation	Usage
Procurement Group Inquiry	AM_PO_GROUP_INQ	Asset Management, Send/Receive Information, Procurement Group Inquiry, Procurement Group Inquiry	Review and Monitor Procurement Groups and their status. Similar inquiry pages exist within Purchasing and Payables.

Pre-AM Financial Page and Pre-AM Physical Page

Use the Pre-AM Financial page (INTFC_PRE_AM_02) to review the asset financial data in the pre-interface table.

Navigation

Asset Management, Send/Receive Information, Preview AP/PO Information, Pre-AM Financial.

Image: Pre-AM Financial Page

This example illustrates the fields and controls on the Pre-AM Financial Page. You can find definitions for the fields and controls later on this page.

Load Status

Displays the current status of the pre-interface row for the asset ID. Values are:

- Pending: Transaction Pending.

- **PO Group Incomplete:** Procurement Group is incomplete. All items within a procurement group sequence have not yet been received. See [Consolidating Requisition and Purchase Order Lines for Asset Components](#).
- *Consolidated:* Transaction consolidated.
- *Errored:* Transaction errors. See error message for details.
- *Excluded:* Transaction is being excluded from Asset Management due to the asset cost not meeting the corresponding capitalization threshold. A detailed message appears in the *Error Message* field. Additionally, the system inserts an entry in the audit table.
- *In Process:* Transaction in process.
- *Loaded:* Transaction loaded.
- *On Hold:* Transaction on hold. Set this status manually to prevent the processing of some rows if you are expecting another event to occur before running.
- *Replaced:* Transaction replaced by other interface records.
- *Unitized:* Transaction unitized (not loaded).

Note: The Load Status field is an editable field, except when the status is PO Group Incomplete.

Note: When all items in a Procurement Group Sequence are received, the Load Status field on the Pre-AM Financial page is updated from *PO Group Incomplete* to *Pending*.

Use the Pre-AM Physical page (INTFC_PRE_AM_01) to review the physical asset data loaded in the pre-interface (Pre-AM 1) table.

Navigation

Asset Management, Send/Receive Information, Preview AP/PO Information, Pre-AM Physical.

Image: Pre-AM Physical Page

This example illustrates the fields and controls on the Pre-AM Physical Page. You can find definitions for the fields and controls later on this page.

Procurement Group ID

Displays the Procurement Group ID for the asset, if applicable.

A procurement group ID is an identifier that is used to associate multiple related purchased items for an asset. The Procurement Group ID can be assigned to a group of procurement transaction lines on a single purchase order or across multiple purchase orders. See [Consolidating Requisition and Purchase Order Lines for Asset Components](#)

Seq (sequence)

Displays the Procurement Group Sequence number. Each transaction within a procurement group ID is assigned a procurement group sequence number.

Primary Unit

Displays the item that is the designated primary unit for the asset. The primary unit for the procurement group ID is assigned on the Procurement Group page. When an item is flagged as a primary item, a separate transaction is inserted into INTFC_PRE_AM in increments of the unit allocation quantity or amount and has its own sequence number.

Asset Management enables you to add assets from existing POs and receipts or from existing accounts payable vouchers.

Note: If the fields on this page are changed, the voucher data may not match the PeopleSoft Asset Management data. In this case, the load status of the inconsistent rows should be set to *Errored*. You should then correct the voucher and resend it to PeopleSoft Asset Management. Physical information can be changed here because it does not affect capitalization or depreciation. In case AMPS1000 sets the status to *Errored*, you need to check the message log on the process monitor for the error message. Care should be taken to keep these changes in sync with purchasing and receiving data.

This table provides a step-by-step example of how a typical transaction flows from Purchasing to Asset Management:

Step	PeopleSoft Application	Page	Notes
Enter a PO.	Purchasing	Purchase Order - Form	Select the supplier, buyer, item, unit of measurement, and amount. Click Defaults to access the Purchase Order Defaults page.
Enter Asset Management information.	Purchasing	Purchase Order Defaults	Enter the AM unit and asset profile ID. Deselect the Capitalize check box if you want to send assets to Asset Management with a status of To be Capitalized. Click OK.
Select all lines from Purchasing.	Purchasing	Purchase Order Defaults	This action returns you to the Purchase Order - Form page.
Select Matching.	Purchasing	Purchase Order - Form	In the Go To region of the page, select <i>11-Matching</i> from the drop-down list box.
Select Match Action and Match Rules.	Purchasing	PO Matching	NA
Dispatch the PO.	Purchasing	Dispatch Purchase Orders	NA
Create receipts.	Purchasing	Receiving (RECV_WPO_AM)	Click Asset Information.
Assign the tag number, serial ID, and asset ID.	Purchasing	Receiving: Asset Information (RECV_WPO_AM)	Select the appropriate icons, and save the page.
Process receipts.	Purchasing	Process Receipts	NA
View your asset transactions to be processed.	Asset Management	Load Preview - Pre AM 1	NA
Run the Purchasing/Payables Interface to load the Transaction Loader tables.	Asset Management	Purchasing/Payables Interface	NA
Run the Transaction Loader to load the Asset Management tables.	Asset Management	Transaction Loader Request	NA
Review the asset in Asset Basic Information.	Asset Management	Asset Acquisition Detail	You should see an acquisition row for each asset.

Related Links

"Understanding Adding and Maintaining Assets (*PeopleSoft FSCM 9.2: Asset Management*)"

Procurement Group Inquiry Page

Use the Procurement Group Inquiry page (AM_PO_GROUP_INQ) to review procurement group details and statuses.

Navigation

Asset Management, Send/Receive Information, Procurement Group Inquiry, Procurement Group Inquiry.

Image: Procurement Group Inquiry Page

This example illustrates the fields and controls on the Procurement Group Inquiry Page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Procurement Group Inquiry' page. It features a 'Selection Criteria' section with various input fields and dropdown menus. Below this is a 'Procurement Group Detail' table with columns for AM Unit, Asset ID, Description, Load Status, Group Seq, Pre-Interface ID, Line, and Load Type. The table contains two rows of data.

AM Unit	Asset ID	Description	Load Status	Group Seq	Pre-Interface ID	Line	Load Type
1 US001	NEXT	Rooftop Unit	Pending	2	6	1	
2 US001	NEXT	Coil Guards	Pending	2	5	1	

Selection Criteria

Enter any criteria for the procurement group for which you want to review details.

Procurement Group ID

Select to limit your search results to a specific procurement group ID. A procurement group ID is an identifier used to associate multiple related purchased items. The Procurement Group ID can be assigned to a group of procurement transaction lines on a single purchase order or across multiple purchase orders. See [Consolidating Requisition and Purchase Order Lines for Asset Components](#).

Data Source

Select one of the following data sources if you want to further limit your search results:

- Pre-interface – select to view procurement group details of data that resides in the Pre-Interface table after running the Receiver Interface Push Application Engine process (PO_RECVPUSH) in Purchasing or the Load Assets Application Engine process (INTFAPAM) in Payables.

- Interface – select to view procurement group details of data that resides in the Transaction Loader tables after running the Payables/Purchasing Interface process (AMPS1000).
- Asset Acquisition Detail – select to view procurement group details of data that resides in the Asset Management tables after running the Transaction Loader process (AMIF1000).

Procurement Group Detail

Group Seq (group sequence)	Displays the Procurement Group Sequence number.
Unit	Displays the Asset Management Business Unit.
PO	Click this link to drill into the PO_LINE_INQ page. See "Purchase Order Inquiry Page (<i>PeopleSoft FSCM 9.2: Payables</i>)"
Voucher	Drill to AP_VOUCHER_INQUIRY. See "Voucher Inquiry Page (<i>PeopleSoft FSCM 9.2: Payables</i>)"

Payables/Purchasing Interface Page

Use the Payables/Purchasing Interface page (RUN_AMPS1000) to run the Pre-Interface Loader to load the data (from Payables or Purchasing) into the Asset Management Loader tables.

Navigation

Asset Management, Send/Receive Information, Retrieve Info from AP/PO

When running this process, be aware of how the Pre-Interface Loader and the Transaction Loader each handles multisource transactions:

- In a three-way match between a PO, a receipt, and a voucher, where they are all asset-related, the receipt must be processed into the Asset Management Pre-Interface Loader table earlier than, or at the same time as, the voucher record.

The receipt can be processed by the Pre-Interface Loader at the same time, but the voucher cannot be processed by the Pre-Interface Loader before the receipt. This ensures that you are not paying for assets before they are received.

- Ensure that the Pre-Interface Loader and the Transaction Loader have fully processed any previous runs before you run the Pre-Interface Loader again.

If you haven't fully processed the Transaction Loader after running the Pre-Interface Loader, you can create duplicate assets. The Pre-Interface Loader checks for assets that have been added from Receiving when a voucher is processed through the interface in order to avoid creating duplicate assets. The system does not look in the interface tables, therefore, if the Transaction Loader has not yet processed any previous runs of the Pre-Interface Loader. The result is that these unprocessed assets will not be available in the acquisition detail tables to perform matching.

This table provides a more detailed step-by-step example of how a typical transaction flows from Payables to Asset Management. In this example, Payables receives data from Purchasing:

Step	PeopleSoft Application	Page	Notes
Create a voucher by copying the receiver or PO.	Payables	Voucher - Invoice Information (VCHR_EXPRESS)	Click Copy PO/Recv. This action opens the Voucher Copy Worksheet.
Manually associate receivers if only the PO is copied onto the voucher.	Payables	Voucher - Invoice Information (VCHR_EXPRESS)	Click the Associate Receivers link.
Select the PO or receiver unit and receiver ID that you want to pay, and click the Copy PO button.	Payables	Voucher - Invoice Information (VCHR_EXPRESS)	After clicking the Copy PO button, you are returned to the Voucher-Invoice Information page.
Verify that the item is ready for matching.	Payables	Voucher Attributes (VCHR_STATUS_IA)	In the Match Action group box, <i>Ready</i> should appear as the status.
Match processes.	Payables	Match Request	NA
Verify that no receiver exceptions exist.			NA
Verify that the voucher can be posted.	Payables	Voucher Attributes - Matched Vouchers	NA
Post the voucher.	Payables	Voucher Posting Request	NA
Verify that <i>Posted</i> appears as the voucher post status.	Payables	Voucher Inquiry	NA
Run the Load Assets process.	Payables	Load Assets Request	This loads Payables transactions to the Pre-Interface table.
Review and correct data if necessary.	Asset Management	Load Preview - Pre AM 1	NA
Run the Purchasing/Payables Interface to load the Transaction Loader tables.	Asset Management	Purchasing/Payables Interface	NA
Review and correct the data if necessary.	Asset Management	Financials Transactions and Physical Transaction A	NA
Run the Transaction Loader to load the Asset Management tables.	Asset Management	Transaction Loader Request	NA
Verify the asset cost on the Cost History page.	Asset Management	Asset Cost History (ASSET_TRANS_01)	You should see a cost row for each book of the related profile ID.

Step	PeopleSoft Application	Page	Notes
Review the asset in Asset Basic Information, and verify that the asset is capitalized.	Asset Management	Asset Acquisition Detail	You should see an acquisition row for each asset. The row from the PO is retained, not updated, and a new row from Payables is added.

Note: The Purchasing interface process does not check for non-PO received assets when processing vouchers for PeopleSoft Asset Management.

Related Links

"Setting Up Procurement Groups (*PeopleSoft FSCM 9.2: Purchasing*)"

"Creating Purchase Order Lines (*PeopleSoft FSCM 9.2: Purchasing*)"

"Creating Requisition Lines (*PeopleSoft FSCM 9.2: Purchasing*)"

"Receive Page (*PeopleSoft FSCM 9.2: eProcurement*)"

Integrating with PeopleSoft Project Costing

This topic provides an overview of integrating PeopleSoft Asset Management with PeopleSoft Project Costing.

Understanding PeopleSoft Project Costing Integration

Assets that originate in Project Costing are usually the outcome of construction projects. They can accumulate cost information associated with salvage and removal costs, proceeds from sales, and the like.

When you establish integration between PeopleSoft Asset Management and PeopleSoft Project Costing, you can perform the following processes from PeopleSoft Project Costing:

- Set up express capitalization.
- Set up manual capitalization.
- Define express assets and relate them to projects.
- Capitalize assets by using express capitalization.
- Capitalize assets by using manual capitalization.
- Review and approve assets.
- Retire assets.

PeopleSoft Project Costing can also send cost information to PeopleSoft Asset Management for group assets that have not yet been consolidated. The cost for unrealized assets is accumulated as a pseudo group member asset, and depreciated at the group asset level.

Project Costing sends asset information directly to the Asset Management Loader Tables (INTFC_FIN and INTFC_PHY_A) by means of the Project Costing-Asset Management Integration Application Engine process (RUN_PC_AM). This enables you to depreciate costs with a project before its completion.

Note: PeopleSoft Asset Management creates transactions in Asset Management tables from other feeder systems by using the Transaction Loader (AMIF1000) application engine. Transactions for existing assets that have a status of *Retired* or *Transferred* are not passed through the Transaction Loader; they are processed within their respective components.

Once you have transferred data from Project Costing, you can preview data in the loader tables, approve the load lines, approve the interface ID, and run the Transaction Loader process to transfer the data into Asset Management tables.

- The Transaction Loader tables load using the express automated process.
- The approval of the data in the Transaction Loader tables can be set to automatically approve or to require manual review and approval.
- The Transaction Loader Approval interface enables you to review and cancel the process.

You can then go back to the source systems to correct data that may not be loading as anticipated.

The Transaction Loader process can run automatically when:

- Asset profiles have been defined.
- Unitization and consolidation rules have been defined for the project.
- Items have been defined as serialized or nonserialized.
- Asset Capitalization triggering rules have been established for the project.
 - One or more assets have been created from the project costs and put in service.
 - Depreciation schedules have been activated so that depreciation expenses are generated.
 - The assets have been updated in the Asset Repository.
 - Parent-child and component relationships have been established among the assets if needed.
 - Adjustments to assets have been recorded so that an existing asset's values reflect accurately.

Note: If you are sending parent-child assets from Project Costing, the Transaction Loader relies on information that you have defined on the Asset Definition page of the Capitalize Project Assets component to accurately create the asset definition in Asset Management. If you have identified an existing parent asset for the asset that you are capitalizing from Project Costing, the Transaction Loader automatically creates a child asset. If you enter an asset ID in Project Costing, and also enter that same asset ID in the Parent ID field and it does not exist in the Asset Management PARENT_ASSET table, Transaction Loader creates a parent asset.

Related Links

"Understanding Asset Capitalization Processes (*PeopleSoft FSCM 9.2: Project Costing*)"

Integrating with Strategic Sourcing

This topic provides an overview of integrating Asset Management with Strategic Sourcing.

Understanding Integrating with Strategic Sourcing


When a sale is initiated by Strategic Sourcing, information required to bill for the auctioned asset is made available to Asset Management and sent to Billing (if applicable). Processing transactions in multiple currencies is also available.

If you integrate with Billing, you can generate billing invoices for assets sold at auction. This link provides a conduit for accessing customer information when you are generating billing invoices.

This process map shows the typical data flow between these products:

Image: Asset Management integration to Strategic Sourcing data flow

Data flow between Asset Management and Strategic Sourcing:



Note: Strategic Sourcing does not process all types of assets. Any assets tagged as hazardous material or that have been retired, transferred, or subjected to reinstatement, or that are subject to VAT are not processed by Strategic Sourcing. The Strategic Sourcing statuses are available within the Asset Basic Add page. These are *Sold in Auction*, *Sent to Auction*, *Not Allowed to be Auctioned*, and *Allowed to be Auctioned*.

Related Links

"Putting Assets up for Auction (*PeopleSoft FSCM 9.2: Asset Management*)"

Previewing Data in the Loader Tables

This topic provides an overview of previewing data in the loader tables and discusses how to:

- Preview the financial loader tables.
- Preview physical data in the loader tables.

Pages Used to Preview Data in the Loader Tables

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Financial Transactions	INTFC_FIN_01	Asset Management, Send/Receive Information, Approve Financial Information, Review	View data in the financial loader table.
Physical Transactions A	INTFC_PHY_A	Asset Management, Send/Receive Information, Approve Physical Information, Review A	View data in the physical loader table.
Physical Transactions B	INTFC_PHY_B	Asset Management, Send/Receive Information, Approve Physical Information, Review B	View data in the physical loader table. This table and page are mainly used during conversion.

Understanding Previewing Data in the Loader Tables

The most common way to transfer data to Asset Management is to populate two loader tables, Financial (INTFC_FIN) and Physical A (INTFC_PHY_A). These tables are typically populated when you:

- Run the Payables/Purchasing interface to upload data from Purchasing or Payables.
- Run the Asset Management integration process from Projects.
- Run mass changes in Asset Management.
- Convert data from a previous fixed asset system to Asset Management.
- Dispose of assets using the disposal worksheet.
- Make impairments and revaluations through worksheet pages.
- Receive financial transactions from Maintenance Management business processes.
- Upload assets using the Excel to CI feature.

You can view data loaded into these tables, giving you the opportunity to preview the data to be loaded into Asset Management when you run the Transaction Loader.

Financial Transactions Page

Use the Financial Transactions page (INTFC_FIN_01) to view data in the financial loader table.

Navigation

Asset Management, Send/Receive Information, Approve Financial Information, Review

Interface ID	Identifies the interface process that populated the table.
Interface Line Number	Displays the row that you are viewing in the table.
PI ID (physical inventory ID)	Displays the physical inventory control ID. A value appears if the transactions were generated by the Physical Inventory process (AMPI1000).
Mass Change Definition	Displays the mass change definition used if you populated this table by running a mass change.
Auto Approval Status (automatic approval status)	This check box is selected if you set the Approved field to a value of <i>Y</i> in the loader table (when converting); if the transactions came from Purchasing, Projects, or Payables and you selected Auto Approval on the AM Specific Fields page of the Asset Mass Change component; or if you selected Auto Approval on the physical inventory control ID. If this check box is not selected, you must approve the interface ID manually.
Asset ID	When the asset ID is set to <i>NEXT</i> , the next asset number for your business unit is assigned to this asset when you run the Transaction Loader. If the asset is subject to split-funding treatment, a subidentifying sequence number is appended to the asset ID. These are assigned when you retrieve information from Purchasing or Payables.
Load Type/Status	<p>Values are:</p> <ul style="list-style-type: none"> • <i>Consolidated</i>: Transaction consolidated. • <i>Errored</i>: Transaction errors. See error message for details. • <i>Excluded</i>: Transaction is being excluded from Asset Management due to the asset cost not meeting the corresponding capitalization threshold. A detailed message appears in the <i>Error Message</i> field. Additionally, the system inserts an entry in the audit table. • <i>In Process</i>: Transaction in process. • <i>Loaded</i>: Transaction loaded. • <i>On Hold</i>: Transaction on hold. Set this status manually to prevent the processing of some rows if you are expecting another event to occur before running. • <i>Pending</i>: Transaction pending.

- *Replaced:* Transaction replaced by other interface records.
- *Unitized:* Transaction unitized (not loaded).

See [Running the Transaction Loader](#).

The Financial Transactions page (INTFC_FIN) displays financial information and associated ChartFields one row at a time. This is the data that the Transaction Loader uses to populate the Asset Management tables; after you review it, you can make changes as needed depending on your editing permissions established at the user preferences level.

Note: The Transaction, Accounting, In Service, Acquisition and Placement Dates assigned to an asset component reflect the date that the Procurement Group Sequence is completely received. This date is expected to fall in the current open accounting period.

Warning! You can update conversion data (by using SQL) or other financial data that has not been calculated by a program. However, when data has been calculated by a mass change, you should not change the Payables/Purchasing interface or the Capitalize Project Assets interface without careful consideration of the implications of such changes. Any information that you manually update could cause integrity problems and you must be certain that you understand the changes you are making before you make them.

Physical Transactions A Page and Physical Transactions B Page

Use the Physical Transactions A page (INTFC_PHY_A) and the Physical Transactions B page (INTFC_PHY_B) to view data in the physical loader table.

Navigation

Asset Management, Send/Receive Information, Approve Physical Information, Review A or Review B

Image: Review-A Page

This example illustrates the fields and controls on the Review-A Page. You can find definitions for the fields and controls later on this page.

Preview the data and complete the appropriate fields.

Interface ID

Identifies the interface process that populated the table.

Line Num (line number)

Displays the row that you are viewing in the table.

PI ID (physical inventory ID)

Displays the physical inventory control ID. A value appears if the transactions were generated by the Physical Inventory process (AMPPI1000).

MC Defn ID (Mass Change Definition ID)

Displays the mass change definition used if you populated this table by mass change.

Auto Approval Status (automatic approval status)

This check box is selected if you set the Approved field to a value of Y in the loader table (when converting); if the transactions came from Purchasing, Projects, or Payables and you selected Auto Approval on the AM Specific Fields page of the Asset Mass Change component; or if you selected Auto Approval on the physical inventory control ID. If this check box is not selected, you must approve the interface ID manually.

Asset ID

When the asset ID is set to *NEXT*, the next asset number for your business unit is assigned to this asset when you run the

Transaction Loader. If the asset is subject to split-funding treatment, a subidentifying sequence number is appended to the asset ID. These are assigned when you retrieve information from Purchasing or Payables.

Load Type/Status

Values are:

- *Consolidated*: Transaction consolidated.
- *Errored*: Transaction errors. See error message for details.
- *Excluded*: Transaction is being excluded from Asset Management due to the asset cost not meeting the corresponding capitalization threshold. A detailed message appears in the Error Message field. Additionally, the system inserts an entry in the audit table.
- *In Process*: Transaction in process.
- *Loaded*: Transaction loaded.
- *On Hold*: Transaction on hold. Set this status manually to prevent the processing of some rows if you are expecting another event to occur before running.
- *Pending*: Transaction pending.
- *Replaced*: Transaction replaced by other interface records.

Unitized: Transaction unitized (not loaded).

See [Load Transactions into AM Page](#)

Procurement Group ID

Displays the Procurement Group ID for the asset. A procurement group ID is an identifier that is used to associate multiple related purchased items for an asset. The Procurement Group ID can be assigned to a group of procurement transaction lines on a single purchase order or across multiple purchase orders. See [Consolidating Requisition and Purchase Order Lines for Asset Components](#)

Seq (sequence)

Displays the Procurement Group Sequence number. Each transaction within a procurement group ID is assigned a procurement group sequence number.

Primary Unit

Displays the item that is the designated primary unit for the asset. The primary unit for the procurement group ID is assigned on the Procurement Group page. When an item is flagged as a primary item, a separate transaction is inserted into INTFC_PRE_AM in increments of the unit allocation quantity or amount and has its own sequence number.

Approving Load Lines

This topic discusses how to:

- Approve financial load line interface IDs.
- Approve physical interface IDs.

Although most records appear preapproved, you may need to approve all pending interface IDs before loading them into the Asset Management tables. The Interface Asset Information component includes pages on which you can approve pending interface IDs.

Pages Used to Approve Load Lines

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Approve Financial	INTFC_FIN_APPR	Asset Management, Send/Receive Information, Approve Financial Information, Approve	Approve the data in the financial loader table. The page displays a summary of all the interface IDs pending approval in the financial loader table.
Approve Physical A	INTFC_PHY_APPR_A	Asset Management, Send/Receive Information, Approve Physical Information, Approve-A	View data in the physical loader table.
Approve Physical B	INTFC_PHY_APPR_B	Asset Management, Send/Receive Information, Approve Physical Information, Approve-B	View data in the physical loader table. This table and page are mainly used during conversion.

Approve Financial Page

Use the Approve Financial page (INTFC_FIN_APPR) to approve the data in the financial loader table.

The page displays a summary of all the interface IDs pending approval in the financial loader table.

Navigation

Asset Management, Send/Receive Information, Approve Financial Information, Approve

Intfc ID (interface ID)

Identifies by number the interface process used to populate the financial loader table.

Unit

Reflects the business unit that receives these transactions when you run the Transaction Loader.

PI ID (physical inventory ID)

Appears if you have populated the financial loader table by generating reconciliation transactions as part of a physical inventory process.

Transaction/Interface Load ID and Load Type

Load lines are summarized by these fields. The load type is much like the trans type, but provides a greater level of detail. Each trans type in PeopleSoft Asset Management can generate several different load types.

This table displays some load types (those marked with an asterisk are uncommon):

<i>Load Type</i>	<i>Long Name</i>	<i>Financial or Physical</i>
AAD	Additional Cost Add	Financial
ACQ	Insert Acquisition Detail	Physical *
ADD	Asset Add	Financial
ADJ	Asset Cost Adjustment	Financial
ADP	Asset Depreciation Write-off	Financial
ADQ	Adjust Cost & Add Acquisition Detail	Financial and physical *
ARA	Add Retired Asset	Financial and physical
ASD	Asset Deletion	Financial and physical
AUP	Asset Information Update	Physical
BKD	Book Deletion	Financial *
BKS	Book Change	Financial
BSD	Selective Book Delete	Financial *
CAP	Asset Capitalization	Financial
CLC	Custodian/Location Change	Physical *
CLS	Closed Voucher	Financial
CIC	Capitalize into Composite	Financial
CN1	Conversion of First Book	Financial and physical
CN2	Conversion of Subsequent Books	Financial
FAD	Financial and Physical Add	Financial
GRP	Group Asset Add	Financial and physical
IHI	(Physical) Inventory History Insert	Physical
IUI	InterUnit Transfer, In Side	Financial and physical
IUO	InterUnit Transfer, Out Side	Financial

Load Type	Long Name	Financial or Physical
LAD	Leased Asset Add	Financial and physical *
NAD	Non-financial Add	Physical
REN	Non-capital Retire	Physical
TRN	Non-capital Transfer	Physical
REL	Operating Lease Retire	Physical
TRO	Operating Lease Transfer	Physical
OPT	Open Transaction Generation	Not applicable *
PHY	Physical Asset Change	Physical
PRT	Partial Retirement	Financial
RAQ	Replace Acquisition Detail	Physical
RCT	Asset Recategorization	Financial
REI	Asset Reinstatement	Financial
RET	Asset Retirement	Financial
RNA	Retired Non-financial Asset	Physical
TRF	Intra-Business Unit Transfer	Financial

Approve Physical A Page and Approve Physical B Page

Use the Approve Physical A page (INTFC_PHY_APPR_A) to view data in the physical loader table.

Use the Approve Physical B page (INTFC_PHY_APPR_B) to view data in the physical loader table.

These tables and pages are mainly used during conversion.

Navigation

Asset Management, Send/Receive Information, Approve Physical Information, Approve-A or Approve B.

Review and complete the applicable fields.

Running the Transaction Loader

This topic provides an overview of the Transaction Loader run process and discusses how to run the Transaction Loader (AMIF1000).

Page Used to Run the Transaction Loader

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Load Transactions into AM	RUN_AMIF1000	Asset Management, Send/Receive Information, Load Transactions, Load Transactions into AM, Load Transactions into AM	Run the Transaction Loader process.

Understanding the Transaction Loader Run Process

The Transaction Loader reads data staged in the loader tables and populates Asset Management tables with the data. Use the Transaction Loader whenever the loader tables have been populated as a result of integration with other applications or conversion from a previous fixed-asset system, or to complete data updates processed by a mass change or physical inventory.

Note: If you are converting from a previous fixed-asset system, you must run the Transaction Edit program (AMIFEDIT) before running the Transaction Loader. The Transaction Edit program performs edit checks on the data fields that you specify to help ensure that the information that you load into Asset Management is correct. Review the data loaded into INTFC_FIN, INTFC_PHY_A, and INTFC_PHY_B, and view the Transaction Loader (AMIF1000) carefully before you run it. You may need to change some of the data defaults that it contains.

If you are using the Transaction Loader to integrate information from Purchasing or Payables, you may want to consolidate or unitize load lines. This is necessary only if you are unable to use the serialization characteristics in the item master catalog. If you choose to do so, consolidation or unitization must be completed before you run the Transaction Loader.

Note: Serialization is not supported in Asset Management from PeopleSoft Payables for quantities greater than one (as it is from PeopleSoft Purchasing.)

For converted assets and assets loaded through the Transaction Loader, the default is to book accumulated depreciation to the *previous* period. However, if you complete the START_PD, END_PD, and FISCAL_YEAR fields on the Financial Loader table (INTFC_FIN) with the values for the current period, and the amount in the DEPR field is not 0, any accumulated depreciation is booked to the *current* period.

Load Transactions into AM Page

Use the Load Transactions into AM page (RUN_AMIF1000) to run the Transaction Loader process.

Navigation

Asset Management, Send/Receive Information, Load Transactions, Load Transactions into AM, Load Transactions into AM

Image: Load Transactions into AM page

This example illustrates the fields and controls on the Load Transactions into AM page. You can find definitions for the fields and controls later on this page.

The screenshot shows the 'Load Transactions into AM' page with the following sections:

- Run Control Parameters:** Includes fields for *Request ID (1), Interface ID (0), AM Business Unit, Process Frequency (Don't), To Interface ID (0), System Source, and a checkbox for Process AM Integration.
- Find Trans Load ID (optional):** Includes fields for System Source, AM Business Unit, Load Type, and Load Status (Pending). It also has radio buttons for Financial Record and Physical Records, and a Search button.
- Interface Information Table:** A table with columns: Interface ID, System Source, Load Type, AM Business Unit, Load Description, Load Status, and Total Items in Query. The table is currently empty.

Run Control Parameters

System Source

One load ID may come from multiple system sources—for example, from both PeopleSoft Purchasing and PeopleSoft Payables. To run *all* lines with the same load ID, leave the System Source field blank. To process only PeopleSoft Billing, Payables, or the Purchasing load lines with the ID, and so on, then enter that system.

AM Business Unit

Select to run the transaction loader for a given business unit, or leave this field blank to run the process for all AM business units.

Process AM Integration

Select this option to process component change-out integration from PeopleSoft Maintenance Management. This selection appears only if you have PeopleSoft Maintenance Management installed and is not related to the interface line numbers. You can leave the interface line numbers as zero and select this option to process the pending requests. If you do not select this option, the transaction loader does not process Maintenance Management transactions

Find Trans Load ID (optional)

If you do not already know the interface ID that you want to process, the Transaction Loader enables you to search for transactions based on system source, load type, AM business unit, load status, and whether they consist of physical or financial records. You can use as many or as few of these criteria as you want. The more you use, the narrower your search is.

The load status can be one of the following values. Enter the appropriate value:

Load Status	Definition
<i>Consolidate</i> (consolidated)	Transactions Consolidated (will not be loaded).
<i>Errored</i>	Transaction Errors Note: To rerun transactions in status <i>Errored</i> , you have to change the load status to <i>Pending</i> .
<i>Excluded</i>	Transaction is being excluded from Asset Management due to the asset cost not meeting the corresponding capitalization threshold. A detailed message appears in the <i>Error Message</i> field that states that the capitalization threshold for this profile has determined that this is an expense and will not generate an asset ID. Additionally, the system inserts an entry in the audit table. See Capitalization Thresholds Page . See Capitalization Thresholds Page .
<i>In Process</i>	Processing is ongoing.
<i>Loaded</i>	Transactions Loaded
<i>On Hold</i>	Transactions are not processed. Set this status manually to prevent the processing of some rows if you are expecting another event to occur before running.
<i>Pending</i>	Transactions Not Loaded
<i>Replaced</i>	Transaction line replaced with alternate line.
<i>Unitized</i>	Transactions Unitized (will not be loaded)

Consolidating and Unitizing Assets

This topic provides an overview of consolidating and unitizing assets and discusses how to:

- Consolidate assets using the Procurement Group ID.

- Consolidate assets from the Consolidate Assets - FROM Assets page.
- Consolidate and save your new asset as a load line from the Consolidate Assets - TO Assets page.
- View detailed information on the load line that you selected from the Unitizing Assets - FROM Assets page.
- Specify any details for proportional unitization from the Proportional Unitization Defaults page.
- Define the individual assets into which you want this load line unitized, and view totals and balances.

Pages Used to Consolidate and Unitize Assets

Page Name	Definition Name	Navigation	Usage
Consolidate Assets - FROM Assets	ASSET_CONSOL_01	Asset Management, Send/Receive Information, Load Transactions, Consolidate Assets	Consolidate assets with an action of Add.
Consolidate Assets - TO Asset	ASSET_CONSOL_02	Asset Management, Send/Receive Information, Load Transactions, Consolidate Assets, TO Asset	Consolidate and save your new asset as a load line.
Unitize Assets - FROM Asset	ASSET_UNIT_01	Asset Management, Send/Receive Information, Load Transactions, Unitize Assets	View detailed information on the load line that you selected.
Proportional Unitization Defaults	ASSET_UNIT_01A	Click the EZ Unitize button on the Unitize Assets - FROM Assets page.	Specify details for proportional unitization.
Unitize Assets - TO Assets	ASSET_UNIT_02	Asset Management, Send/Receive Information, Unitize Assets, TO Assets	Define individual assets into which you want this load line unitized.
Unitization Totals	ASSET_UNIT_SP	Click the Totals/Balance link on the Unitize Assets - TO Assets page.	View totals and balances.

Understanding the Consolidation and Unitization of Assets

When you run the Transaction Loader, each pending load line generates a unique asset in PeopleSoft Asset Management. If you want to consolidate many load lines into a single asset, or split a load line into many assets (unitize) manually, you must do so *before* running the Transaction Loader.

You can, however, enable the system and set up Procurement Groups to automate the asset consolidation process. If you enable and implement procurement groups, the Transaction Loader processes the Procurement Groups by sequence number to identify which interface lines correspond to an individual asset.

See [Consolidating Requisition and Purchase Order Lines for Asset Components](#)

The system enables you to unitize or consolidate financial or physical asset load lines. You may have one line that actually represents several different assets; for example, you may pay for 10 computers with one voucher line. If you run the PeopleSoft Payables Interface without unitizing, this voucher line becomes one pending load line for one asset, and the quantity is equal to 10. To generate *several* assets, you must first unitize the single load line into 10 separate lines. Then when you run the Transaction Loader, each load line generates one asset; that is, 10 assets are created, each having a quantity equal to one.

See “Allocating Asset-Applicable Voucher Adjustments” in "Understanding Asset-Applicable Vouchers (PeopleSoft FSCM 9.2: Payables)"

Note: Establishing items in the master catalog with serialization attributes can save you much time by making the unitization and consolidation step unnecessary. If you want unitized assets when receiving or generating the voucher for items with multiple quantities (receiver and voucher lines have a quantity greater than one), establish those items as serialized. If your items should not be considered an asset unless their quantity is greater than one—for example, a dozen—then establish those items as nonserialized. Even if you do not use the item master catalog for other business processes, you may want to set up your asset items in the catalog as a one-time setup activity.

This documentation discusses consolidating and unitizing assets rather than load lines. However, you should remember that the assets don't actually exist until you run the Transaction Loader.

Consolidate Assets - FROM Assets Page

Use the Consolidate Assets - FROM Assets page (ASSET_CONSOL_01) to consolidate assets with an action of Add.

Navigation

Asset Management, Send/Receive Information, Load Transactions, Consolidate Assets

This page enables you to add and search for consolidation-from assets with a particular value by using these search fields:

Field	Description
<i>Activity</i>	Activity ID derived from PeopleSoft Project Costing.
<i>Asset Category</i>	Asset Category
<i>AP Business Unit</i>	Payables Business Unit
<i>Budget Reference</i>	Budget Reference
<i>Class Field</i>	Class Field
<i>Department</i>	Department
<i>Fund Code</i>	Fund Code
<i>Invoice Number</i>	Invoice - from PeopleSoft Payables
<i>Interface ID</i>	Interface ID

Field	Description
<i>Interface Line Number</i>	Interface Line Number
<i>Item ID</i>	Inventory Item - from PeopleSoft Payables
<i>Operating Unit</i>	Operating Unit - from PeopleSoft General Ledger
<i>PO Business Unit</i>	Purchasing Business Unit
<i>PO Number</i>	Purchase Order - from PeopleSoft Purchasing
<i>Product</i>	Product
<i>Program Code</i>	Program Code
<i>Project</i>	Project - from Project Costing, Purchasing, or Payables.
<i>Receipt Line</i>	Receiver - from PeopleSoft Purchasing
<i>Receipt Number</i>	Receiver line number - from PeopleSoft Purchasing.
<i>Receiving Business Unit</i>	Receiving Business Unit from PeopleSoft Purchasing
<i>Supplier ID</i>	Supplier
<i>Voucher ID</i>	Voucher - from Payables

You use different search fields when consolidating lines from different systems. For example, when consolidating lines from PeopleSoft Payables, you can use Voucher ID. When consolidating lines from Purchasing, you can use PO Number. If you enter *Invoice Number*, the system prompts you to select from a list of invoice numbers; if you enter *PO Numbers*, you receive a list of PO numbers.

Enter the search field that you want to use, and then enter the value to search for. Data retrieval is based on combined keys; therefore, you are prompted to supply a business unit.

Note: You can define row-level security for the selection fields to limit searches by role or permission list.

Note: Rows continue to be added to the scroll area on page 1, based on the field and value combination actions. Delete unwanted rows.

Image: Consolidate Assets - FROM Assets page

This example illustrates the fields and controls on the Consolidate Assets - FROM Assets page. You can find definitions for the fields and controls later on this page.

Default	To Exclude	Unit	Profile ID	Asset ID	Threshold ID	Oper Unit	Fund	Dept	Program	Class	Bud Ref	P
<input type="checkbox"/>	<input type="checkbox"/>	US006		LEAST08								
<input type="checkbox"/>	<input type="checkbox"/>	US006	FURNITURE	FINADD01	CT_001							
<input type="checkbox"/>	<input type="checkbox"/>	US006		FINADD01								
<input type="checkbox"/>	<input type="checkbox"/>	US006		FINADD02								
<input type="checkbox"/>	<input type="checkbox"/>	US006		FINADD03								
<input type="checkbox"/>	<input type="checkbox"/>	US006		FINADD04								
<input type="checkbox"/>	<input type="checkbox"/>	US006		FINADD04								
<input type="checkbox"/>	<input type="checkbox"/>	US006		FINADD05								
<input type="checkbox"/>	<input type="checkbox"/>	US006		NEXT								
<input type="checkbox"/>	<input type="checkbox"/>	US006	FURNITURE	FINBASC01	CT_001							

FROM Asset Tabs

Chartfields

Review ChartField information related to the load line.

Cost

Review cost information related to the load line.

Interface

Review interface information, including the interface line, about the load line.

Select the Default check box to designate the default row. The default row is the one from which values are copied when you access the TO Asset page.

Select the To Exclude check box for each asset that you want to exclude from consolidation. Then click the Exclude button. The assets that remain are the ones that are transferred to the TO Asset page for consolidation. Upon accessing the TO Asset page, all the rows in the grid at the time are consolidated using the information from the row that is designated as the default row to generate the new asset.

Note: Oracle recommends that you not change the value of the profile ID so that you can delete rows from the search grid on each tab in the component.

Consolidate Assets – TO Asset Page

Use the Consolidate Assets - TO Asset page (ASSET_CONSOL_02) to consolidate and save your new asset as a load line.

Navigation

Asset Management, Send/Receive Information, Load Transactions, Consolidate Assets, TO Asset

Enter information about your asset if appropriate. Most of the fields on this page are optional fields.

The values displayed in the Cost, Sales Tax, Freight, and Use Tax fields equal the sum of the value for all of the consolidated from assets.

To complete the consolidation process, load the resulting load transaction by using the Transaction Loader.

Unitize Assets – FROM Asset Page

Use the Unitize Assets - FROM Asset page (ASSET_UNIT_01) to view detailed information on the load line that you selected.

Navigation

Asset Management, Send/Receive Information, Load Transactions, Unitize Assets

Verify that this is the line that you want to unitize, then click EZ Unitize to access the Proportional Unitization Defaults page, where you can proportionally unitize.

Note: Unitizing interface rows that contain a default PROFILE_ID equal to N (multibook assets) prompts unitization of all books. The cost of the other books for each new asset is based on the percent cost of the unitized book.

Proportional Unitization Defaults Page

Use the Proportional Unitization Defaults page (ASSET_UNIT_01A) to specify details for proportional unitization.

Navigation

Click the EZ Unitize button on the Unitize Assets - FROM Assets page.

Note: If you enter a quantity but no description or profile at the prompt, these values appear by default from the Unitize From page.

The Unitize Assets - TO Assets page appears, and the system automatically inserts new load lines in the scroll region based on the prompt information that you entered. You do not have to separate out the assets manually. All of the amounts are prorated.

Unitize Assets – TO Assets Page

Use the Unitize Assets - TO Assets page (ASSET_UNIT_02) to define individual assets into which you want this load line unitized.

Navigation

Asset Management, Send/Receive Information, Unitize Assets, TO Assets

Certain information on this page appears by default from the originating system.

Information for assets that originated in PeopleSoft Payables appears by default for these fields:

- Business Unit

- Voucher
- Voucher Line
- Invoice
- Cost
- Base Cost
- Sales Tax
- Base Sales Tax Amount
- Use Tax
- Base Use Tax Amount
- Freight
- Base Freight Amount
- Base Merchandise Amount
- VAT Non Recoverable (nonrecoverable value-added tax)
- Non-Recoverable Base Amount
- Recoverable VAT (recoverable value-added tax)
- VAT Recovery Base Amount

Note: These fields appear only after you have entered a profile ID and have moved the cursor out of that field or used the EZ Unitize function.

Information for assets that originated in Purchasing appears by default for these fields:

- Profile ID
- Business Unit
- PO No. (purchase order number)
- Cost
- Quantity

Information for assets that originated in Projects appears by default for these fields:

- Profile ID
- Business Unit
- Project
- Activity

Click the Totals/Balance link to access the Unitization Totals page, where you can view totals and balances.

To complete the unitization process, load the resulting load lines by using the Transaction Loader.

Exporting Property Tax Data to Third-Party Tax Systems

Companies are required to submit property tax in each jurisdiction where they operate and own property. When organizations have multiple locations in different taxing jurisdictions, this requirement is increasingly burdensome to the tax department. Many corporations have purchased third-party property tax software to manage and calculate their property tax and to file their returns. PeopleSoft Asset Management enables you to export property-related asset information to third-party property tax systems such as Vertex, Taxware, and Property Tax Management Systems. An SQR program populates a property tax table for export to third-party property tax systems. Which data fields are selected for export is based upon the import file requirements of Vertex, but you can easily modify this to suit those of other property tax suppliers.

Export property tax information from the Load Property Tax Table page to export property tax data to third-party tax systems.

You can also build your own export table definition and export by using the PeopleTools Query utility.

Page Used to Export Property Tax Data to Third-Party Tax Systems

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Load Property Tax Table	RUN_LDPRPTAX	Asset Management, Financial Reports, Load Reporting Tables, Load Property Tax Table	Export property tax information.

Load Property Tax Table Page

Use the Load Property Tax Table page (RUN_LDPRPTAX) to export property tax information.

Navigation

Asset Management, Financial Reports, Load Reporting Tables, Load Property Tax Table

Note: While viewing and exporting data from the PS_PROPERTY_TAX table, note that the RETIREMENT_DT field in this table is used for both transfers out and retirements. When the asset is retired, a retirement date appears. For the assets that have been transferred out, a transfer transaction date appears, with the TRANS_IN_OUT switch set to O.

Importing Asset Data by Using the Excel to Component Interface Utility

PeopleSoft Asset Management provides the option to use a utility program that employs a delivered PeopleSoft Asset Management template and Microsoft Excel spreadsheets to upload asset information in batches. You can use the interface to upload asset information from a spreadsheet template when adding multiple assets to your database and to add setup data into the system.

The following component interfaces (CI) are provided by PeopleSoft Asset Management:

- Asset class (ASSET_CLASS_CI)
- Hazardous asset definition (ASSET_FSC_DEFN_CI)
- Category (CATEGORY_DEFN_CI)
- Depreciation schedule (DEPR_SCHEDULE_DEFN_CI)
- Depreciation terms (DEPR_TERMS_DEFN_CI)
- InterUnit Definition (IU_TRF_DEFN_TBL_CI)
- Operator Defaults for AM (OPR_DEFAULT_AM_CI)
- Asset Profile (PROFILE_CI)
- Non Financial Retirement (RETIRE_NF_CI)
- Non Financial Retirement - Backup (RETIRE_NF_CI_BKUP)
- User Defined Depreciation Rates (UD_DEPR_RATE_CI)
- Add transaction to asset financial and physical tables (INTFC_FINPHY_SS_A)
- Fair Value addition (AM_FV_CI)

When you are using the INTFC_FINPHY_SS_A component interface, the data is loaded to INTFC_FIN and INTFC_PHY_A tables. Three interface types are allowed: CN1, CN2, and FAD. The default profile switch can be on or off. A preview page for the asset data enables you to preview the imported information from the spreadsheet. Finally, a PeopleTools component interface is delivered, enabling you to upload asset *Add* transactions into the PeopleSoft Asset Management database.

To import asset information to the database by using the Excel to Component Interface spreadsheets:

1. Connect to the PeopleTools Excel spreadsheet utility interface.
2. Define the Microsoft Excel template that you are importing.
3. Complete the Microsoft Excel spreadsheet template with the data to be imported for new assets.
4. Preview the data to be imported from the asset import preview page.
5. Select the component interface, and submit the data for addition to the database.

Detailed information about using the Excel to Component Interface utility appears in the PeopleTools product documentation.

Related Links

"Understanding Adding and Maintaining Assets (*PeopleSoft FSCM 9.2: Asset Management*)"

"PeopleSoft Asset Management Overview (*PeopleSoft FSCM 9.2: Asset Management*)"

Configuring PeopleSoft Asset Lifecycle Management Background Processes

Configuring PeopleSoft Asset Lifecycle Management Background Processes

This topic discusses how to configure temporary tables for batch processing.

Configuring Temporary Tables for Background Processing

When you run background batch processes in parallel, you risk data contention and deadlocks on temporary tables. To avoid this, PeopleTools enables you to dedicate specific instances of temporary tables for each process. When PeopleSoft Application Engine manages a dedicated temporary table instance, it controls the locking of the table before use and the unlocking of the table after use.

When you decide how many temporary table instances to dedicate for a process, consider the number of temporary tables that the process uses. More instances result in more copies of the temporary tables on the system. For example, if a process uses 25 temporary tables and you have 10 instances for a process, you will have 250 temporary tables on the system.

If you run processes in parallel and all of the dedicated temporary table instances are in use, the performance of the process decreases. You need to find a balance that works for your organization.

Note: When number of instances is specified, PeopleSoft Application Designer displays a list of the temporary tables for the process. Use the list to determine how many temporary tables each process uses.

Specify how many temporary table instances to dedicate for each of the following batch processes that can run in parallel in PeopleSoft Asset Management:

- Load Transactions (AMIF1000).
- Calculate Depreciation (AM_DEPR_CALC).
- Group Asset Consolidation (AMGRPCON)
- Create Accounting Entries (AM_AMAEDIST).
- Asset IU Processor (AM_IU_PRCS)
- Close Depreciation (AM_DPCLOSE).
- Depreciation Reporting (AMDPREPT).
- Payables/Purchasing Interface (AMPS1000).

- Cost Summarization (AM_COST_SUM).
- CGU Impairment (AM_CGU_IMP).
- What-if Depreciation (AM_DEPR_COMP).
- Revaluation in Mass (AMREVAL and AMDEPRWRTOFF)
- Capitalization Threshold Validation (AM_CAPVAL)

The PeopleTools documentation discusses the usage of temporary tables in detail and describes how to specify the number of instances.

If you run any of the General Ledger COBOL processes, also configure the temporary tables for those processes. The *PeopleSoft General Ledger* product documentation discusses how to do this in detail.

See also *PeopleTools: Application Engine* product documentation.

Related Links

"Understanding Optimal General Ledger Performance (*PeopleSoft FSCM 9.2: General Ledger*)"

Setting Up and Using Approval Framework in Asset Management

Understanding Approval Framework in Asset Management

This topic provides an overview of Approval Framework for PeopleSoft Asset Management based on PeopleSoft Enterprise Components Approval Framework (AF) and discusses how to:

- [Complete the Approval Transaction Registry and Configuration.](#)
- [Create or modify notification template definitions.](#)
- [Define user lists for approval framework.](#)
- [Set up approval process definitions \(rules\).](#)
- [Examples: Setup and Approval of Asset Transactions Using Approval Framework.](#)

PeopleSoft Approval Framework is a feature that provides a configurable framework and page interface with which to implement the workflow approval process. PeopleSoft Asset Management uses the Approval Framework (with multi-level approval capabilities) for its approval of Asset Disposals.

Note: PeopleSoft Asset Management does not upgrade approval history data from prior functionality to the current Approval Framework approval data.

PeopleSoft Financials delivers much of the Approval Framework setup, either as system data or demo data. However, some changes are necessary to tailor your workflow requirements to your organization through using the components described in this topic. You need to activate the workflow and adjust the approval setup to identify your individual users, templates, and servers. After an asset disposal is initiated from the Disposal Worksheet, for example, the system routes the transaction to the approvers. Approvers can view and take action in two ways: using their Worklist page or navigating directly to the Asset Disposal Worksheet page.

During the approval process these actions take place:

- The system notifies approvers that a pending action needs their attention.
- Approvers access the transaction details, provide comments, and take action (approve or deny asset disposal, for example).
- The system checks for additional routings in the same routing path. If all steps have been completed for the stage, then the next step is started in the next stage. If multiple routing paths exist, the system routes them in parallel.
- Once all approvers of a disposal have approved it, the Approval Framework notifies the PeopleSoft Asset Management application and the disposal is processed.


For more information, see *PeopleSoft: Approval Framework*.

Approval Framework Process Flow in Asset Management

This diagram outlines the steps in the inspection and assessment of the delivered setup and the required considerations to set up and implement workflow using the Approval Framework in your environment.

Image: High Level Approval Framework Process Flow for Asset Management

High Level Approval Framework Process Flow for Asset Management



Use of the Approval Framework requires the inspection of the delivered registration definitions, the approval configuration definitions, and the approval templates for changes that are necessary for your particular installation. Although sample business processes, activities, and business events are delivered with the product, you may need to modify and tailor them to your specific implementation requirements.

In addition to enabling the Approval Framework, you define the Asset Management approval user lists and Asset Management approval process rules.

Completing the Approval Transaction Registry and Configuration

This section discusses how to:

- Complete the AM approval transaction registry.
- Complete the AM approval transaction configuration.

Pages Used to Complete the Approval Transaction Registry and Configuration

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Register Transactions	EOAW_TXN	Enterprise Components, Approvals, Approvals, Transaction Registry, Register Transactions	Defines the integration between Asset Management and the Approval Framework (AF) by process ID and is delivered with system data.
Configure Transactions	EOAW_TXN_NOTIFY	Enterprise Components, Approvals, Approvals, Transaction Configuration, Configure Transactions	Defines the details of the integration between Asset Management and the Approval Framework (AF) by process ID and is delivered with system data.

Register Transactions Page

Use the Register Transactions page (EOAW_TXN) to define the integration between Asset Management and the Approval Framework (AF) by process ID. Values are delivered with system data.

Navigation

Enterprise Components, Approvals, Approvals, Transaction Registry, Register Transactions

Image: Register Transactions page (1 of 2)


This example illustrates the fields and controls on the Register Transactions page (1 of 2). You can find definitions for the fields and controls later on this page.

Register Transactions

Process ID **AMDisposal**

*Description

Owner ID

*Cross Reference Table 


Worklist Prefix


▼ Notification Options

*Enable Notifications


*Notification Strategy


Use Email Approvals:


Form Generator Package Root 

Form Generator Class Path 


▼ Internal URL Definition


Internal URL Base 


Internal Portal Name 

Internal Node Name 


▼ External URL Definitions

External URL Base 

External Portal Name 

External Node Name 

▼ Default Approval Component

*Menu Name 


*Approval Component 

Image: Register Transactions page (2 of 2)

This example illustrates the fields and controls on the Register Transactions page (2 of 2). You can find definitions for the fields and controls later on this page.

▼ **Approval Event Handler Class**

Root Package ID

Class Path

▼ **Approval Status Monitor**

Adhoc Package Adhoc Class

Thread Package Thread Class

▼ **Transaction Approval Levels**

	*Level	*Record (Table) Name		
1	Header ▼	<input style="width: 80%;" type="text" value="AM_DISP_AF_HWW"/>	+	-
2	Line ▼	<input style="width: 80%;" type="text" value="AM_DISP_AF_LNVW"/>	+	-

Level Record Key Field Label IDs

	Record (Table) Name	Field Name	*Field Label ID
1	AM_DISP_AF_HWW	DATE_SUBMITTED	<input style="width: 80%;" type="text" value="DATE_SUBMITTED"/>
2	AM_DISP_AF_HWW	DTTM_STAMP	<input style="width: 80%;" type="text" value="DTTM_STAMP"/>
3	AM_DISP_AF_HWW	ORIGINATOR_ID	<input style="width: 80%;" type="text" value="ORIGINATOR_ID"/>
4	AM_DISP_AF_LNVW	ASSET_ID	<input style="width: 80%;" type="text" value="ASSET ID"/>
5	AM_DISP_AF_LNVW	BUSINESS_UNIT	<input style="width: 80%;" type="text" value="BUSINESS_UNIT"/>
6	AM_DISP_AF_LNVW	DATE_SUBMITTED	<input style="width: 80%;" type="text" value="DATE_SUBMITTED"/>
7	AM_DISP_AF_LNVW	DTTM_STAMP	<input style="width: 80%;" type="text" value="DTTM_STAMP"/>
8	AM_DISP_AF_LNVW	ORIGINATOR_ID	<input style="width: 80%;" type="text" value="ORIGINATOR_ID"/>

[Expand/Collapse All](#)

The Register Transactions page provides the integration between Asset Management and Approval Framework. PeopleSoft Asset Management delivers the AMDisposal process ID with system data.

For AMDisposal, line (asset) level approvals have been defined using the Level field in the Transaction Approval Levels group box.

Note: Do not alter or otherwise modify delivered definitions.

See "Setting Up the Transaction Registry (*PeopleSoft 9.2: Approval Framework*)"

Configure Transactions Page

Use the Configure Transactions page (EOAW_TXN_NOTIFY) to define the details of the integration between Asset Management and the Approval Framework (AF) by process ID.

Navigation

Enterprise Components, Approvals, Approvals, Transaction Configuration, Configure Transactions

Image: Configure Transactions page - (Event for final approval)

This example illustrates the fields and controls on the Configure Transactions page - (Event for final approval). You can find definitions for the fields and controls later on this page.

Configure Transactions

Process ID AMDisposal

Ad Hoc Approver Options

*Approval User Info View PSOPRDEFN_VW

Ad Hoc User List

User Utilities

User Utilities Package

User Utilities Path

Events Find | View All First 5 of 10 Last

*Event On Final Approval *Level Line

Menu Name MANAGE_ASSETS

Approval Component AM_DISPOSAL_APPR

Page Name AM_DISP_APPR01

Menu Action Update

SQL Object Identifier AM_DISP_AF_LN_INFO

Notifications Personalize | Find | View All First 1 of 1 Last

Main	Template Details	Frequency	
*Participant	Channel	User List	Template Name
1 Requester	Email		AMDisposalLineApproved

Notice in the example that the Approval Component is the Approve Disposals (*PeopleSoft FSCM 9.2: Asset Management*) component (AM_DISPOSAL_APPR).

See also, [Example of Approval Framework Setup for Asset Disposal](#).

PeopleSoft delivers line event definitions. Scroll horizontally or click View All to see all the delivered events:

- On Final Approval
- On Final Denial
- Hold Step
- Route For Approval
- Push Back

- On Reassign

Note: Do not alter or otherwise modify delivered event definitions.

See "Configuring Approval Transactions (*PeopleSoft 9.2: Approval Framework*)"

Creating or Modifying Notification Template Definitions

Template definitions provide the email content for approval notifications and are delivered in PeopleSoft Asset Management.

You can modify the verbiage or create your own template definitions. However, you must keep the delivered template variables, unless you create your own SQL objects that are referenced on the configuration definition. Using Approval Framework for Asset Management enables you to create or modify the AMDisposalLineRequest, AMDisposalLineApproved, and the AMDisposalLineDenied routing template definitions for asset disposal.

Pages Used to Create or Modify Notification Templates

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Generic Template Definition	WL_TEMPLATE_GEN	PeopleTools, Workflow, Notifications, Generic Templates, Generic Template Definition	Define or modify approval notification templates that are used in the Approval Framework (AF) (configurable workflow) process.

Creating or Modifying the Approval Routing Template Definition

PeopleSoft delivers generic notification templates for Asset Disposal:

<i>Asset Disposal</i>
<ul style="list-style-type: none"> • AMDisposalLineRequest • AMDisposalLineApproved • AMDisposalLineDenied

Generic Template Definition Page - AM Disposal Line Request Template

Use the Generic Template Definition page - AM Disposal Line Request template to define or modify approval notification templates that are used in the Approval Framework (AF) (configurable workflow) process.

Navigation

PeopleTools, Workflow, Notifications, Generic Templates, Generic Template Definition

Image: Generic Template Definition page – AM Disposal Line Request template

This example illustrates the fields and controls on the Generic Template Definition page – AM Disposal Line Request template.

Generic Template Definition
Blackberry Email Responses

Template: AMDisposalLineRequest

***Description:** Asset Disposal Request

Instructional Text: Type names or email addresses in the To, CC, or BCC fields, using a semi-colon as a separator. Click LOOKUP RECIPIENT to search for a name. Click DELIVERY OPTIONS to view or change the

Priority: 2-Medium

***Sender:** User **Email ID:**

Subject: Asset Disposal Request

Message Text: DATE_SUBMITTED: %2
DTTM_STAMP: %3
ORIGINATOR_ID: %4
BUSINESS_UNIT: %5
ASSET_ID: %6

LINK:
%1

Below is the list of available variables for this template.
You can use template variables within your subject or message text.
The following variables can also be used:
%Date, %DateTime, %Time, %ServerTimeZone, %EmailAddress, %NotificationPriority, %NotificationToList, %NotificationCCList

Template Variables			
*Value	*Description		
%1	URL	+	-
%2	DATE_SUBMITTED	+	-
%3	DTTM_STAMP	+	-
%4	ORIGINATOR_ID	+	-
%5	BUSINESS_UNIT	+	-
%6	ASSET_ID	+	-

Generic Template Definition Page - AM Disposal Line Approved Template

Use the Generic Template Definition page - AM Disposal Line Approved template to define or modify approval notification templates that are used in the Approval Framework (AF) (configurable workflow) process.

Navigation

PeopleTools, Workflow, Notifications, Generic Templates, Generic Template Definition

Image: Generic Template Definition page – AM Disposal Line Approved Template

This example illustrates the fields and controls on the Generic Template Definition page – AM Disposal Line Approved Template.

Generic Template Definition
Blackberry Email Responses

Template: AMDisposalLineApproved

***Description:**

Instructional Text:

Priority:

***Sender:** **Email ID:**

Subject:

Message Text:

Below is the list of available variables for this template.
You can use template variables within your subject or message text.
The following variables can also be used:
%Date, %DateTime, %Time, %ServerTimeZone, %EmailAddress, %NotificationPriority,
%NotificationToList, %NotificationCCList

Template Variables			
*Value	*Description		
<input type="text" value="%1"/>	<input type="text" value="URL"/>	<input type="button" value="+"/>	<input type="button" value="-"/>
<input type="text" value="%2"/>	<input type="text" value="DATE_SUBMITTED"/>	<input type="button" value="+"/>	<input type="button" value="-"/>
<input type="text" value="%3"/>	<input type="text" value="DTTM_STAMP"/>	<input type="button" value="+"/>	<input type="button" value="-"/>
<input type="text" value="%4"/>	<input type="text" value="ORIGINATOR_ID"/>	<input type="button" value="+"/>	<input type="button" value="-"/>
<input type="text" value="%5"/>	<input type="text" value="BUSINESS_UNIT"/>	<input type="button" value="+"/>	<input type="button" value="-"/>
<input type="text" value="%6"/>	<input type="text" value="ASSET_ID"/>	<input type="button" value="+"/>	<input type="button" value="-"/>

Generic Template Definition Page – AM Disposal Line Denied Template

Use the Generic Template Definition page - AM Disposal Line Denied template to define or modify approval notification templates that are used in the Approval Framework (AF) (configurable workflow) process.

Navigation

PeopleTools, Workflow, Notifications, Generic Templates, Generic Template Definition

Image: Generic Template Definition page – AM Disposal Line Denied Template

This example illustrates the fields and controls on the Generic Template Definition page – AM Disposal Line Denied Template.

Generic Template Definition
Blackberry Email Responses

Template: AMDisposalLineDenied

***Description:**

Instructional Text:

Priority:

***Sender:** **Email ID:**

Subject:

Message Text:

Below is the list of available variables for this template.
You can use template variables within your subject or message text.
The following variables can also be used:
%Date, %DateTime, %Time, %ServerTimeZone, %EmailAddress, %NotificationPriority,
%NotificationToList, %NotificationCCList

Template Variables			
*Value	*Description		
<input type="text" value="%1"/>	<input type="text" value="URL"/>	+	-
<input type="text" value="%2"/>	<input type="text" value="DATE_SUBMITTED"/>	+	-
<input type="text" value="%3"/>	<input type="text" value="DTTM_STAMP"/>	+	-
<input type="text" value="%4"/>	<input type="text" value="ORIGINATOR_ID"/>	+	-
<input type="text" value="%5"/>	<input type="text" value="BUSINESS_UNIT"/>	+	-
<input type="text" value="%6"/>	<input type="text" value="ASSET_ID"/>	+	-

Defining User Lists for Approval Framework

This section discusses how to define user lists and asset owners.

Pages Used to Define User Lists or Asset Owners

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
User List Definition	EOAW_USER_LIST	Enterprise Components, Approvals, Approvals, User List Setup, User List Definition	Define user sources for use in the AF approval process (rules).
User Profile - Roles	USER_ROLES	PeopleTools, Security, User Profiles, User Profiles, Roles	List the users that are to be requesters, or approvers for a given role that is accessed by a User List Definition within the Approval Framework.
Roles - Members	ROLE_MEMBER	PeopleTools, Security, Permissions and Roles, Roles, Members	Verify that the role name is assigned to the correct user IDs.
Asset Owner User	AM_OWNER_DEFN2	Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Define Asset Owners, Asset Owner User	Assign users to asset owners. This step is required when using asset disposal.

User List Definition Page


Use the User List Definition page to define user sources for use in the AF approval process (rules).

Navigation

Enterprise Components, Approvals, Approvals, User List Setup, User List Definition

Image: User List Definition page

This example illustrates the fields and controls on the User List Definition page. You can find definitions for the fields and controls later on this page.



The approval user list defines user sources for use with steps in the approval processes (rules).

You can modify and use the delivered user list definitions or set up your own approver user list definition to accommodate your organizational needs.

PeopleSoft delivers the following User Lists for Asset Disposal.

Asset Disposal/User List Source
AMDisposalRequesters / SQL Definition
AMDisposalApprovers / Role
Supervisor by UserId / SQL Definition

Asset Owner User Page

Use the Asset Owner User page to assign users to asset owners. This step is required when using asset disposal.

Navigation

Set Up Financials/Supply Chain, Product Related, Asset Management, Financials, Define Asset Owners, Asset Owner User

Image: Asset Owner User Page

This example illustrates the fields and controls on the Asset Owner User page.

Asset Owner		Asset Owner User	
Asset Owner	Description		
SUPERVISOR1	San Francisco Office Superviso		
Asset Owner User		Personalize	Find
		First	1-2 of 2 Last
*User ID	Retire Approval Required	Show Cost	
1 DVP1	<input checked="" type="checkbox"/>	<input type="checkbox"/>	+ -
2 VP1	<input type="checkbox"/>	<input checked="" type="checkbox"/>	+ -

The asset owner definition is required for asset disposal approval framework. When defining an asset owner user that will be used in the Approval Framework process, be sure to use an asset owner that is not considered a super user (such as MANAGER); otherwise, the disposal will be auto-approved.

See: [Example of Approval Framework Setup for Asset Disposal](#).

For more information, see [Asset Lifecycle Management, Establishing Asset Processing, Establishing Asset Ownership](#).

Setting Up Approval Process Definitions

To set up approval processes, use the Approval Process Setup component.

This section discusses how to:

- Define approval processes.
- Define approval criteria.
- Define paths for approval processes.
- Define steps for approval processes.

Pages Used to Define Approval Process Rules

<i>Page Name</i>	<i>Definition Name</i>	<i>Navigation</i>	<i>Usage</i>
Setup Process Definitions	EOAW_PRCO_MAIN	Enterprise Components, Approvals, Approvals, Approval Process Setup, Setup Process Definitions	Define the stages, paths and steps of the approval definition process.
Criteria Definition	EOAW_CRITERIA	Enterprise Components, Approvals, Approvals, Approval Process Setup, Setup Process Definitions, Definition Criteria, Criteria Definition	Define field and monetary criteria to be used in the approval process.
Approval Path Definition	EOAW_PATH_SEC	Click the Details link within the Paths group box of the Setup Process Definitions page.	Define approval path details, such as time-related escalation options and reassignment.
Approval Step Definition	EOAW_STEP_SEC	Click the Details icon within the Steps group box of the Setup Process Definitions page.	Define approval step details, such as approvers and approver requirements.

Setup Process Definitions Page


Use the Setup Process Definitions page to define the stages, paths and steps of the approval definition process.

Navigation

Enterprise Components, Approvals, Approvals, Approval Process Setup, Setup Process Definitions

Image: Setup Process Definitions Page

This example illustrates the fields and controls on the Setup Process Definitions Page. You can find definitions for the fields and controls later on this page.



Business analysts use this page to define approval definition processes. The process is made up of stages and their paths and steps. The approval steps that you place on the approval path represent the approval levels that are required for a transaction. The approval process definition provides the details of application approval rules. Asset management delivers the following demo Setup Process Definitions for AMDisposal:

- AMLLineApproval (multi-level approvals)
- SHARE (single level approval)

Click the Details icon to access the [Approval Step Definition page](#) and view or modify the User List selection and other approver details.

Note: Note: These definitions are available in the demo database. You may clone and modify them accordingly.

Criteria Definition Page

Use the Criteria Definition page to define field and monetary criteria to be used in the approval process, if needed.

Navigation

Enterprise Components, Approvals, Approvals, Approval Process Setup, Setup Process Definitions, Definition Criteria, Criteria Definition

Criteria entered on this page determines which definition ID is to be used to process the approval. For more information, see Enterprise Components, PeopleSoft Approval Framework documentation, "Understanding the Approval Framework Feature (*PeopleSoft 9.2: Approval Framework*)".

Approval Path Definition Page

Use the Approval Path Definition page to define approval path details, such as time-related escalation options and reassignment.

Navigation

Click the Details link within the Paths group box of the Setup Process Definitions page.

After adding a path (or paths) on the Setup Process Definitions page, use this page to set up additional parameters that determine how the system processes this approval path. Use the Escalate Options to define time elements to be used when an approver requires too much time to approve or deny a pending request.

For more information, see Enterprise Components, PeopleSoft Approval Framework documentation, "Understanding the Approval Framework Feature (*PeopleSoft 9.2: Approval Framework*)".

Approval Step Definition Page

Use the Approval Step Definition page to define approval step details, such as approvers and approver requirements.

Navigation

Click the Details icon within the Steps group box of the Setup Process Definitions page.

Image: Approval Step Definition Page

This example illustrates the fields and controls on the Approval Step Definition Page. You can find definitions for the fields and controls later on this page.

After adding a step (or steps) on the Setup Process Definitions page, use this page to set up additional parameters that determine how the system processes this approval step. The example pictured uses the Supervisor By Userid Approver User List and requires only one approver for the asset disposal.

See [Understanding Approval Framework in Asset Management](#)

See also, *PeopleSoft Enterprise Components: Approval Framework*.

Example of Approval Framework Setup for Asset Disposal

This section discusses the following steps involved in setting up the Approval Framework in Asset Management:

- Review transaction configuration.
- Review or update requester and approvers.
- Assign asset owner permissions.

- Review or update generic templates.
- Review or update approval process setup.
- Review or update transaction configuration.
 - Review the delivered AMDisposal/AMLineApproval transaction configuration definition.
 - Note: Do not alter or otherwise modify this demo definition.

Review or Update Requester and Approvers User Lists

Review delivered user lists for Supervisor by UserID. You want to assign user AMS1 as the first level approver, MGR1 as second level approver, and user AMA1 as the requester. See [Defining User Lists for Approval Framework](#).

In this example, the values are as follows:

1. Verify that the AMA1 User Profile – Workflow page has AMS1 as Supervisor.
2. Verify that the AMS1 User Profile – Workflow page has MGR1 as Supervisor.

Assign Asset Owner Permissions

Define the requestor and approver appropriately on the Define Asset Owners – [Asset Owner User](#) page.

For this example, select the Retire Approval Required check box for the requester (AMA1), and deselect the check box for the approver (AMS1).

See [Pages Used to Define User Lists or Asset Owners](#).

See Asset Lifecycle Management: Establishing Asset Processing, [Establishing Asset Ownership](#).

See also, Approval Framework documentation: Defining Users for Approval Framework.

Review or Update Generic Templates

See [Pages Used to Create or Modify Notification Templates](#).

Check the following generic templates for notification settings:

- AMDisposalLineRequest
- AMDisposalLineApproved
- AMDisposalLineDenied
- AMDisposalLineUpdate

Review or Update Approval Process Setup

See [Setting Up Approval Process Definitions](#).


Example: Request and Approval of Asset Disposal

The following example shows the sequence of an asset disposal routed to the Worklist.

User AMA1 submits the following asset (EX_000000150) for disposal:

Image: Example of the Disposal Worksheet page

This example illustrates the fields and controls on the Disposal Worksheet page. You can find definitions for the fields and controls later on this page.




For more information, see "Initiating Asset Retirement Using the Disposal Worksheet (*PeopleSoft FSCM 9.2: Asset Management*)"

Once the requester, AMA1, submits the selected asset for disposal, the AMDisposal link appears on the approver's worklist (AMS1) as a worklist item from AMA1:

Image: Example of the Worklist Page

This example illustrates the fields and controls on the Example of the Worklist Page. You can find definitions for the fields and controls later on this page.



Clicking the link from the Worklist page, the approver is routed to the Approve Disposals page for approval action:

Image: Example of the Approve Disposals Page

This example illustrates the fields and controls on the Example of the Approve Disposals Page.

Approve Disposals

Originator ?

Originator: AMA1 Name: William Crawford Date Submitted: 10/10/2013

Retirement Overrides ?

Retire Date: 11/21/2013 Disposal Code: Retirement by Sale Accounting Date: 11/21/2013 Default

Approval Action ?

Comments

Disposals Pending Approval ? Personalize | Find | First 1 of 1 Last

Select	Approver Status	Business Unit	Asset ID	Description	Tag Number	Category	Serial ID	Approval Status	View Approval Flow
<input type="checkbox"/>	Approved	US001	AB005	Furniture & Fixtures		FF		Pending	

For more information, see Approve Disposals page, "Initiating Asset Retirement Using the Disposal Worksheet (*PeopleSoft FSCM 9.2: Asset Management*)"